

Oracle® Revenue Management and Billing
Version 2.5.0.4.0

Server Administration Guide
Revision 9.0

E80755-01
March, 2017

ORACLE®

Oracle Revenue Management and Billing Server Administration Guide

E80755-01

Copyright Notice

Copyright © 2017, Oracle and/or its affiliates. All rights reserved.

Trademark Notice

Oracle and Java are registered trademarks of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

License Restrictions Warranty/Consequential Damages Disclaimer

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure, and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or de-compilation of this software, unless required by law for interoperability, is prohibited.

Warranty Disclaimer

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

Restricted Rights Notice

If this software or related documentation is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, the following notice is applicable:

U.S. GOVERNMENT RIGHTS

Oracle programs, including any operating system, integrated software, any programs installed on the hardware and/or documentation delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware and/or documentation shall be subject to license terms and restrictions applicable to the programs. No other rights are granted to the U.S. Government.

Hazardous Applications Notice

This software is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure the safe use of this software. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software in dangerous applications.

Third Party Content, Products, and Services Disclaimer

This software and documentation may provide access to or information on content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third party content, products, or services.

Preface

About This Document

This document helps you to understand the Oracle Revenue Management and Billing (ORMB) architecture and the concepts required for configuring and using the ORMB application. It explains how to configure and deploy web and business application servers. In addition, it explains how to monitor client machines, web and/or business application servers, and database connections.

Note:

All examples and screen captures are used for publishing purposes only and may vary from the actual values seen at your site.

This document covers Oracle Utilities Application Framework V4.3.0.3.0.

For publishing purposes, the Oracle Revenue Management and Billing product will be referred to as "product" in this document.

All utilities in this guide are multi-platform (unless otherwise indicated). For publishing purposes the commands will be in the format command[.sh] which indicates that the command can be used as command on the Windows platform or command.sh on the Linux/UNIX platforms.

Sections of this manual cover the background processing, aka batch, aspects of the Oracle Utilities Application Framework for completeness only. Sections covering the background processing component are marked with a **BATCH** graphic.

This document now covers aspects of the mobile framework used for mobile based products (Oracle Utilities Mobile Workforce Management and Oracle Realtime Scheduler). The relevant settings for this component are marked with a **MOB** graphic. Not all products use the mobile framework; please refer to the installation guide for clarification.

This document now covers aspects of the bundling of Oracle Service Bus and SOA infrastructure. The relevant settings for this component are marked with **OSB** and **SOA** graphics. Not all products use the Oracle Service Bus and SOA infrastructure natively; please refer to the installation guide for clarification. Refer to the Oracle SOA Suite documentation for more information about these products.

Intended Audience

This document is intended for the following audience:

- System and Database Administrators
- Consulting Team
- Implementation Team

Organization of the Document

The information in this document is organized into the following sections:

Section No.	Section Name	Description
Section 1	Architecture	Describes the architecture of the Oracle Revenue Management and Billing application. It also lists the roles and features of each component.
Section 2	Concepts	Lists and describes the concepts which you need to understand before configuring and using the Oracle Revenue Management and Billing application.
Section 3	Operations	Lists and describes various command line utilities. It also explains how to start and stop the Oracle Revenue Management and Billing environments.
Section 4	Monitoring	Lists and describes the basic monitoring regimes and methods used for the Oracle Revenue Management and Billing application. It also explains how to monitor client machines, web and/or business application servers, and database connections.
Section 5	Configuration	Lists and describes various configuration files available in the Oracle Revenue Management and Billing application. It explains how to configure and deploy web and business application servers. In addition, it explains how to configure Web browser, Inbound Web Services, and batch server.
Section 6	Miscellaneous Operations and Configuration	Lists and describes additional configurations that you may want to perform based on the requirement.
Section 7	Operations from Oracle Enterprise Manager	Lists Oracle Utilities targets which are available for the Oracle Revenue Management and Billing application. It explains how to discover Oracle Utilities and Oracle WebLogic targets. It also explains how to monitor the application using Oracle Enterprise Manager.
Appendix A	Parameters	<p>Lists and describes the parameters of various configuration files, such as:</p> <ul style="list-style-type: none"> • environ.ini • web.xml • spl.properties • hibernate.properties • submitbatch.properties • threadpoolworker.properties <p>It also describes the J2EE filters that you can use in the Oracle Revenue Management and Billing application.</p>

Related Documents

You can refer to the following documents for more information:

Document	Description
<i>Oracle Revenue Management and Billing Version 2.5.0.4.0 Release Notes</i>	Provides a brief description about the new features and enhancements made in this release. It also highlights the bug fixes and known issues in this release.
<i>Oracle Revenue Management and Billing Installation Guide</i>	Lists the pre-requisites, supported platforms, and hardware and software requirements for installing the Oracle Revenue Management and Billing application. It also explains how to install the Oracle Revenue Management and Billing application.
<i>Oracle Revenue Management and Billing Quick Installation Guide</i>	Provides high-level information on how to install the Oracle Revenue Management and Billing (ORMB) application and selected additional software.
<i>Oracle Revenue Management and Billing DBA Guide</i>	Provides information about the Oracle Database Server and Client required for installing the Oracle Revenue Management and Billing database. It explains how to install database with and without demo data. It provides database configuration guidelines including recommended settings for the Oracle Exadata Database machine.
<i>Oracle Revenue Management and Billing Security Guide</i>	Lists the security features available in the Oracle Revenue Management and Billing application. It explains how to configure security for the Oracle Revenue Management and Billing application using the default security features.

You can also refer to the following artifacts on [My Oracle Support](#) using the respective Doc ID or part number:

- *Oracle Utilities Application Framework Performance Troubleshooting Guides* (Doc ID: 560382.1)
- *Native Installation Oracle Utilities Application Framework* (Doc ID: 1544969.1)
- *Environment Management document in the Software Configuration Management series* (Doc ID: 560401.1)
- *ILM Planning Guide* (Doc ID: 1682436.1)
- *Batch Best Practices* (Doc ID: 836362.1)
- *Software Configuration Management Series* (Doc ID: 560401.1)
- *Oracle WebLogic JMS Integration* (Doc ID: 1308181.1)
- *Migrating from XAI to IWS* (Doc ID: 1644914.1)
- *Oracle Identity Manager Interface Configuration File* (Doc ID: 970785.1)
- *Oracle Application Management Pack for Oracle Utilities Overview* (Doc ID: 1474435.1)
- *XAI Best Practices whitepaper* (Doc ID: 942074.1)

Whitepapers

A number of supplemental whitepaper are available for the Oracle Utilities Application Framework based products from My Oracle Support. At the time of publication¹ the following whitepapers are available on specific topics:

Whitepaper	Doc ID
Technical Best Practices	560367.1
Performance Troubleshooting Guideline Series	560382.1
Software Configuration Management Series	560401.1
Security Overview	773473.1
LDAP Integration	774783.1
Interface Integration Overview	789060.1
Single Sign On Integration	799912.1
Architecture Guidelines	807068.1
Batch Best Practices	836362.1
XAI Best Practices	942074.1
Production Environment Configuration Guidelines	1068958.1
What's New In Oracle Utilities Application Framework	1177265.1
Database Vault Integration	1290700.1
BI Publisher Integration Guidelines	1299732.1
Oracle SOA Suite Integration	1308161.1
Oracle WebLogic JMS Integration	1308181.1
Implementing Oracle ExaLogic and/or Oracle WebLogic Clustering	1334558.1
IBM WebSphere Clustering	1359369.1
Oracle Identity Management Suite Integration	1375600.1
Advanced Security Overview	1375615.1
Configuration Migration Assistant Overview	1506830.1
Integration Reference Solutions	1506855.1
Native Installation	1544969.1
Oracle Service Bus Integration	1558279.1
Using Oracle Text for Fuzzy Searching	1561930.1
Audit Vault Integration	1606764.1
Private Cloud Planning Guide	1643845.1

Whitepaper	Doc ID
Migrating from XAI to IWS	1644914.1
ILM Planning Guide	1682436.1
ConfigTools Best Practices	1929040.1
Keystore Configuration	2014161.1

Contents

1. Architecture	1
1.1 Roles and Features	3
1.1.1 Client	3
1.1.2 Web Application Server	4
1.1.3 Business Application Server	4
1.1.4 Database Server	4
1.1.5 Batch Server BATCH	5
2. Concepts	9
2.1 Environment	9
2.1.1 Environment Identifier	9
2.1.2 Server Roles	10
2.2 Administration User ID and Group	10
2.3 Native Support VS Embedded Support	11
2.4 Directory Structure	13
2.5 Software Directory Structure	14
2.5.1 Software (splapp) Directory	17
2.5.2 Tools Directory	18
2.5.3 Directory Permissions	20
2.6 Output Structure	21
2.7 Environment Variables	21
2.8 Common Application Logs	24
2.8.1 Automated Backup of Log Files	25
2.9 Batch Concepts BATCH	26
2.9.1 Batch Clustering Concepts	26
2.9.2 Batch Controls	27
2.9.3 Standard Parameters	27
2.9.4 Additional Key Parameters	29
2.9.5 Batch Run Tree	30
2.9.6 Timed Jobs	30
2.9.7 Level of Service	30
2.9.8 Explanation of Commit Interval	31
2.9.9 Explanation of Thread Limit and Thread Number	32
2.9.10 Explanation of Restart and Rerun	32
2.9.11 Submission Methods	33
3. Operations	36
3.1 Command Line Utilities	36

3.1.1	bedit - Batch Edit BATCH	36
3.1.2	buildJavadocIndex[.sh] - Builds Appviewer Java Docs.....	37
3.1.3	configureEnv – Setup Environment Settings.....	38
3.1.4	createDBStandalone[.sh] - Creates Database Patches	39
3.1.5	extractCMSOURCEUNIX[.sh] - Migrate Code Across Upgrades	40
3.1.6	genappvieweritems – Generate AppViewer.....	41
3.1.7	initialSetup – Maintain Configuration Settings	43
3.1.8	installSFGROUP[.sh] - Install Software Patches	46
3.1.9	invokeDBUpdatePatch[.sh] - Regenerates passwords in Installation Options	47
3.1.10	iwsdeploy - Inbound Web Services Deployment	47
3.1.11	jmxbatchclient[.sh] – JMX Batch Command Line BATCH	47
3.1.12	ouafDatabasePatch[.sh] - Install Database Patches.....	49
3.1.13	PatchDeployUtility[.sh] - Create and Deploy Patch Rollups.....	50
3.1.14	showjavaproc[.sh] - Show Java Processes.....	51
3.1.15	splenviron – Set Environment Variables	52
3.1.16	spl – Start/Stop Environment.....	54
3.1.17	starttpw[.sh] - Start Threadpoolworker.....	55
3.1.18	submitjob[.sh] - Submit Batch Threads BATCH	56
3.1.19	threadpoolworker[.sh] - Manage Threadpools BATCH	59
3.2	Attaching to an Environment	61
3.3	Starting an Environment.....	62
3.3.1	Starting All Tiers on a Single Server	62
3.3.2	Starting/Stopping at Boot Time (UNIX/Linux).....	63
3.4	Stopping an Environment	67
3.4.1	Stopping All Tiers on a Single Server.....	67
3.5	Starting and Stopping Using consoles	68
4.	Monitoring	70
4.1	Monitoring Regimes	70
4.2	Monitoring Client Machines	71
4.2.1	Monitoring the Desktop.....	71
4.2.2	Client Debug Facility.....	72
4.3	Monitoring Web/Business Application Server	74
4.4	JMX Based Monitoring.....	75
4.4.1	Web Application Server JMX Reference	76
4.4.2	Business Application Server JMX Reference	87
4.4.3	Batch JMX Reference	91
4.4.4	JMX Security	98
4.4.5	Extending JMX Security	99
4.4.6	Execution Dump Format	99

4.4.7	Service Lists	100
4.4.8	Resetting Statistics	101
4.5	Database Connection Monitoring	101
4.6	Probe Transaction.....	102
5.	Configuration	103
5.1	Configuration Files.....	103
5.1.1	application.xml – ADF Application Configuration	103
5.1.2	cistab - Global Configuration Files	104
5.1.3	coherence-cache-config.xml - Oracle Coherence Configuration BATCH	105
5.1.4	e0Batch.properties - General Batch Properties BATCH	105
5.1.5	ejb-jar.xml - Enterprise Java Server Beans Configuration.....	105
5.1.6	ENVIRON.INI - Environment Configuration File	105
5.1.7	hibernate.properties - Database Connectivity Settings.....	107
5.1.8	log4j.properties – Product Logging Configuration	108
5.1.9	Server Jar File (ouaf_jar_versions.txt).....	108
5.1.10	spl.properties – Product Behaviour Settings	108
5.1.11	submitbatch.properties - Submitter Configuration BATCH	108
5.1.12	tangosol-coherence-override.xml - Coherence Overrides BATCH	109
5.1.13	threadpoolworker.properties - Threadpool Configuration BATCH	109
5.1.14	web.xml – J2EE Deployment Descriptor	109
5.1.15	weblogic.xml – Oracle WebLogic Extensions	110
5.1.16	weblogic-ejb-jar.xml - WebLogic Extensions for Enterprise Java Server Beans....	113
5.1.17	webservices.xml.resource - Web Services Configuration	113
5.2	Web Browser Configuration	113
5.3	Web Application Server Configuration.....	117
5.3.1	Caveat.....	117
5.3.2	Web Application Server Concepts.....	117
5.3.3	Web Applications	117
5.3.4	Web Application Server Configuration Files	118
5.3.5	Quick Reference Guide for Web Application Server Configuration.....	122
5.3.6	User Interface Backward Compatibility Settings	123
5.3.7	Web Application Server Deployment Process	124
5.4	Business Application Server Configuration	125
5.4.1	Business Application Server Concepts	127
5.4.2	Business Application Server Configuration Files	127
5.4.3	Business Application Server Configuration Process.....	127
5.4.4	Quick Reference Guide for Business Application Server Configuration	131
5.4.5	Business Application Server Deployment Process	131

5.5	Inbound Web Services Configuration.....	133
5.5.1	Enabling Inbound Web Services.....	133
5.5.2	Inbound Web Services Configuration Files	135
5.5.3	Inbound Web Services Concepts.....	136
5.5.4	Inbound Web Services Configuration Process	137
5.5.5	Inbound Web Services Deployment Process	139
5.5.6	Quick Reference Guide for Inbound Web Services Configuration.....	141
5.5.7	Inbound Web Services Deployment Utilities	141
5.6	Batch Server Configuration BATCH	142
5.6.1	Batch Configuration Files	142
5.6.2	General Configuration Process	144
5.6.3	Configuring Batch Using bedit.....	145
5.6.4	Batch Configuration Guidelines	152
5.7	Oracle Cloud Support	154
5.7.1	Support for Host Whitelisting	155
5.7.2	Domain Template Support.....	156
5.7.3	Diagnostics Support (WLDF)	157
5.7.4	ECID Support	159
5.7.5	Global Cache Flush Support	159
5.7.6	Java Flight Recorder Support	160
5.7.7	Work Manager Support	161
5.7.8	Trust Store Support.....	162
6.	Miscellaneous Operations and Configurations	163
6.1	Enabling Email Logging from Log4j.....	163
6.2	Overriding the Default Oracle Database Connection Information.....	164
6.3	Cache Management.....	166
6.3.1	Server Cache	166
6.3.2	Client Cache	167
6.4	Oracle WebLogic: Expanded or Archive Format.....	168
6.5	Implementing Custom Templates	169
6.5.1	Additional Templates	170
6.6	Sending Emails at the Conclusion of Batch Process BATCH	173
6.7	Oracle WebLogic Configuration Support.....	175
6.8	Using Configuration Files Outside the WAR/EAR File.....	176
6.9	Oracle RAC Support	177
6.10	Adding a Custom Privacy Policy Screen.....	178
6.11	IBM WebSphere/WebSphere ND Support	179
6.12	User Exit Include Files.....	181
6.12.1	Properties File User Exits	185

6.13	Custom JMS Configuration	186
6.14	Online Transaction Timeouts	188
6.15	Setting the Date for Testing Purposes.....	190
6.16	Secure Transactions.....	191
6.17	Native Oracle WebLogic Support	192
6.17.1	Manual Re-Deployment Process.....	193
6.18	Oracle WebLogic Console Operations	194
6.18.1	Starting and Stopping from Console	194
6.18.2	Monitoring Web Applications Using the Console	195
6.19	Specifying Custom Log File Names BATCH	196
6.20	Turning Off L2 Cache BATCH	198
6.21	JDBC Support	198
6.22	Cancelling Batch Processes Using JMX BATCH	199
7.	Operations from Oracle Enterprise Manager.....	201
7.1	Discovering Oracle Utilities Targets.....	201
7.2	Discovering Oracle WebLogic Targets	202
7.3	Oracle Utilities Targets	203
7.4	Monitoring Using Oracle Enterprise Manager	204
8.	Oracle Scheduler Integration.....	205
8.1	Introduction.....	205
8.2	Background Materials.....	205
8.3	Oracle Scheduler Interface Overview.....	205
8.3.1	Oracle Scheduler Configuration.....	206
8.3.2	Oracle Scheduler Execution	207
8.4	Oracle Scheduler Interface (OUAF_BATCH)	207
8.4.1	Submit_Job - Submit a Job or Thread	208
8.4.2	Restart_Thread - Restart a Failed Thread/Job	211
8.4.3	Cancel_Job - Cancel a Running Job	211
8.4.4	Set_Option - Set a Global or Job Option	212
8.4.5	Unset_Option - Reset a Global or Job Option.....	214
8.4.6	Raise_Thread_Error - Raise an Error.....	214
8.4.7	Setting Preferences	214
8.4.8	Order of Preference	215
8.4.9	Using soft_parm_map	215
8.4.10	Using soft_parm_list	216
8.5	Building a Schedule.....	217
8.5.1	Recommended Tools	217
8.5.2	Defining Programs.....	218
8.5.3	Defining Job Classes	219

8.5.4	Defining Schedules.....	220
8.5.5	Defining Remote Destinations and Credentials.....	221
8.5.6	Defining Jobs	223
8.5.7	Defining Chains	224
8.5.8	Other Scheduler Objects	225
8.6	Executing Jobs	226
8.7	Monitoring Oracle Scheduler	226
8.7.1	Job States	226
8.7.2	Dictionary Views	226
8.7.3	Scheduler Notifications	226
8.8	Cancellation	227
8.9	Exporting Schedules Across Environments	227
Appendix A :	Parameters.....	228
A.1	Conventions Used in This Section.....	228
A.2	ENVIRON.INI	229
A.2.1	ADDITIONAL_RUNTIME_CLASSPATH - Additional Classpath.....	229
A.2.2	ADDITIONAL_STOP_WEBLOGIC - Additional Stop Arguments	229
A.2.3	ADF_HOME - Location of ADF Software	230
A.2.4	ANT_ADDITIONAL_OPT - Additional Options for ANT	230
A.2.5	ANT_HOME - Location of ANT	230
A.2.6	ANT_OPT_MAX - ANT Maximum Heap Size.....	231
A.2.7	ANT_OPT_MIN - ANT Minimum Heap Size	231
A.2.8	appViewer - Name of appViewer WAR File	231
A.2.9	BATCHDAEMON - Whether Online Batch Daemon is Enabled	232
A.2.10	BATCHEDIT_ENABLED - Whether Batch Edit Facility is Enabled	232
A.2.11	BATCHENABLED - Whether Online Batch Server is Enabled.....	233
A.2.12	BATCHTHREADS - Number of Online Batch Server Threads	233
A.2.13	BATCH_DBPASS - Batch User Password.....	233
A.2.14	BATCH_DBUSER - Batch User.....	234
A.2.15	BATCH_MEMORY_ADDITIONAL_OPT - Threadpool Worker JVM Additional Options	234
A.2.16	BATCH_MEMORY_OPT_MAX - Threadpool Worker Java Maximum Heap Size ...	235
A.2.17	BATCH_MEMORY_OPT_MAXPERMSIZE - Threadpool Worker Java Maximum Perm Size	235
A.2.18	BATCH_MEMORY_OPT_MIN - Threadpool Worker Java Minimum Heap Size.....	236
A.2.19	BATCH_MODE - Default Mode of Batch	236
A.2.20	BATCH_ONLINE_LOG_DIR - Online Batch Submission Log Directory	236
A.2.21	BATCH_RMI_PORT - RMI Port for Batch	237
A.2.22	BSN_APP - Business Server Application Name.....	237

A.2.23	BSN_JMX_RMI_PORT_PERFORMANCE - JMX Port for Business Application Server	237
A.2.24	BSN_JMX_SYSPASS - Password for BAS JMX Monitoring.....	238
A.2.25	BSN_JMX_SYSUSER - Default User for BSN JMX Monitoring.....	238
A.2.26	BSN_NODENAME - IBM WebSphere Node Name	239
A.2.27	BSN_SVRNAME - IBM WebSphere Server Name	239
A.2.28	BSN_WASBOOTSTRAPPORT - Bootstrap Port	239
A.2.29	BSN_WLHOST - Business App Server Host.....	240
A.2.30	BSN_WLS_SVRNAME - Oracle WebLogic Server Name	240
A.2.31	CERT_IDENT_KS_ALIAS - SSL Certificate Keystore Alias.....	240
A.2.32	CERT_IDENT_KS_FILE - SSL Keystore File	241
A.2.33	CERT_IDENT_KS_PWD - SSL Keystore Password.....	241
A.2.34	CERT_IDENT_KS_TYPE - SSL Keystore Type	241
A.2.35	CERT_INSTALL_SCRIPT - Install SSL Keystore	241
A.2.36	CERT_KS - SSL Keystore Type	242
A.2.37	CERT_TRUST_KS_ALIAS - SSL Trust Alias.....	242
A.2.38	CERT_TRUST_KS_FILE - SSL Trust Keystore File	242
A.2.39	CERT_TRUST_KS_PWD - SSL Trust Keystore Password	243
A.2.40	CERT_TRUST_KS_TYPE - SSL Trust Keystore Type.....	243
A.2.41	CLOUD_CUSTOM_WHITE_LIST_PATH - Custom URL Whitelists for Cloud.....	243
A.2.42	CLOUD_RESTRICTIONS_URLS_ENABLE - Enable or Disable URL Restrictions.....	244
A.2.43	CLOUD_WHITE_LIST_PATH - URL Whitelists for Cloud.....	244
A.2.44	CM_INSTALL_SAMPLE - Whether Samples are Installed	244
A.2.45	CMPDB - Database Type	245
A.2.46	COHERENCE_CLUSTER_ADDRESS - Multicast Address for Batch Cluster	245
A.2.47	COHERENCE_CLUSTER_MODE - Batch Cluster Mode	246
A.2.48	COHERENCE_CLUSTER_NAME - Batch Cluster Name	246
A.2.49	COHERENCE_CLUSTER_PORT - Batch Cluster Port Number	247
A.2.50	CONTEXTFACTORY - Context Factory for Mobile Application	247
A.2.51	DBCONNECTION - JDBC Connection String	248
A.2.52	DBDRIVER - Database Driver	248
A.2.53	DBNAME - Database Name	249
A.2.54	DBPASS - Online Database User Password	249
A.2.55	DBPASS_GEOCODE_WLS - GEOFILTER Database Password.....	250
A.2.56	DBPASS_MDS - MDS Database Password	250
A.2.57	DBPASS_ORASDPM - DPM Database Password.....	251
A.2.58	DBPASS_OSB - OSB Database Password	251
A.2.59	DBPASS_SOAINFRA - SOA Database Password.....	252
A.2.60	DBPORT - Database Listener Port	252
A.2.61	DBSERVER - Database Server	253

A.2.62	DBURL_GEOCODE - GEOCODE JDBC URL.....	253
A.2.63	DBURL_OSB - OSB JDBC URL	253
A.2.64	DBURL_SOA - SOA Suite JDBC URL.....	254
A.2.65	DBUSER - Online Database User	254
A.2.66	DBUSER_GEOCODE - GEOCODE Database User	254
A.2.67	DBUSER_MDS - SOA MDS Database User	255
A.2.68	DBUSER_ORASDPM - DPM Database User	255
A.2.69	DBUSER_OSB - OSB Database User.....	256
A.2.70	DBUSER_SOAINFRA - SOA Database User.....	256
A.2.71	DB_OVERRIDE_CONNECTION - Custom JDBC URL.....	257
A.2.72	DESC - Environment Description.....	257
A.2.73	DIALECT - Hibernate Dialect.....	258
A.2.74	DIRSEP - Directory Separator	258
A.2.75	DOC1BILLSCRIPT - Name of External Print Script.....	259
A.2.76	DOC1SCRIPT - Name of Generic Print Script.....	259
A.2.77	ENCODING - Whether Encryption is Enabled.....	260
A.2.78	ENVIRONMENT_ID - Environment Identifier	260
A.2.79	FW_VERSION - Oracle Utilities Application Framework Version	261
A.2.80	FW_VERSION_NUM - Oracle Utilities Application Framework Version Identifier	261
A.2.81	GIS - GIS Support	262
A.2.82	GIS_URL - GIS Service URL.....	262
A.2.83	GIS_WLSYSPASS - GIS WebLogic System Password	263
A.2.84	GIS_WLSYSUSER - GIS WebLogic System User ID	263
A.2.85	GLOBAL_JVMARGS - Additional JVM Arguments.....	264
A.2.86	help - Name of Online Help WAR File	264
A.2.87	HEADEND_CD_CB - Headend System URI for SOA Configuration Plan (CD_CB) ..	265
A.2.88	HEADEND_MR_CB - Headend System URI for SOA Configuration Plan (MR_CB)	265
A.2.89	HIBERNATE_JAR_DIR - Location of Hibernate JAR files	266
A.2.90	HIGHVALUE - Language Specific Highvalues	266
A.2.91	IWS_JDBC_NAME - JNDI Name for the IWS Connection Pools.....	266
A.2.92	IPCSTARTPORT - Starting IPC Port for Scheduler	267
A.2.93	IWSWAR - Name of Inbound Web Services WAR	267
A.2.94	JAVAENCODING - Java Language Encoding.....	267
A.2.95	JAVA_HOME - Location of Java SDK.....	268
A.2.96	JAVA_VENDOR - Java Vendor.....	268
A.2.97	JAVA_VERSION - JVM Version String.....	268
A.2.98	JAVA_VERSION_MAIN - Abbreviated JVM Version.....	269
A.2.99	JDBC_NAME - JNDI Name for the Online JDBC Data Source.....	269
A.2.100	JNDI_GEOCODE - Geocode Data Source JNDI.....	269

A.2.101	JNDI_OSB - OSB Data Source JNDI	270
A.2.102	JVM_ADDITIONAL_OPT - Child JVM Additional Options	270
A.2.103	JVMCOMMAND - Generated Child JVM Command.....	271
A.2.104	JVMMEMORYARG - Child JVM Memory Allocation	271
A.2.105	KS_ALIAS - Key Alias	272
A.2.106	KS_ALIAS_KEYALG - Key Algorithm	272
A.2.107	KS_ALIAS_KEYSIZE - Keysize	272
A.2.108	KS_HMAC_ALIAS - HMAC Key Alias.....	273
A.2.109	KS_HMAC_ALIAS_KEYALG - HMAC Key Algorithm.....	273
A.2.110	KS_HMAC_ALIAS_KEYSIZE - HMAC Keysize.....	273
A.2.111	KS_KEYSTORE_FILE - Keystore File Name	274
A.2.112	KS_MODE - Key Padding Mode	274
A.2.113	KS_PADDING - Key Padding Algorithm	274
A.2.114	KS_STOREPASS_FILE - Key Password Store Pass.....	275
A.2.115	KS_STORETYPE - Key Store Type	275
A.2.116	LD_LIBRARY_PATH - Library Path for Windows/Linux/Solaris.....	276
A.2.117	LIBPATH - Library Path for AIX.....	276
A.2.118	MAPDIR - Location of Map Files Used for Scheduler	276
A.2.119	MAPVIEWER_EAR - Location of Mapviewer EAR File	277
A.2.120	MAPVIEWER_ISLOCAL - Deploy Mapviewer Locally	277
A.2.121	MAXPROCESSINGTIME - Maximum Scheduler Processing Time	278
A.2.122	MINREQUESTS - Initial Scheduler Minimum Requests	278
A.2.123	MOBILITY_APP_ONLY - Deploy Only Mobility Web Application.....	279
A.2.124	MODULES - Names of Modules Installed.....	279
A.2.125	NLS_LANG - NLS Language Setting.....	280
A.2.126	NODEID - Scheduler Node Identifier.....	280
A.2.127	OIM_SPML_NAME_SPACE - OIM Default Namespace	281
A.2.128	OIM_SPML_SOAP_DEBUG_SETTING - OIM Interface Debug	281
A.2.129	OIM_SPML_SOAP_ELEMENT - OIM SOAP Element	282
A.2.130	OIM_SPML_UBER_SCHEMA_NAME - Name of OIM Interface Schema.....	282
A.2.131	ONLINE_DISPLAY_HOME - Location of Print Rendering Software.....	283
A.2.132	ONS_JAR_DIR - Location of Oracle Notification Service Libraries	283
A.2.133	ONSCONFIG - ONS Configuration.....	284
A.2.134	OPEN_SPML_ENABLED_ENV - Whether OIM Interface Enabled.....	284
A.2.135	OPSY - Operating System	284
A.2.136	ORACLE_CLIENT_HOME - Oracle Client Home.....	285
A.2.137	OSB_HOME - Oracle Service Bus Home	285
A.2.138	OSB_HOST - Oracle Service Bus Host Name	286
A.2.139	OSB_LOG_DIR - Default Location for Oracle Service Bus Logs.....	286

A.2.140	OSB_PASS_WLS - Password for Oracle Service Bus.....	287
A.2.141	OSB_PORT_NUMBER - Oracle Service Bus Port Number.....	287
A.2.142	OSB_USER - User Name for Oracle Service Bus	288
A.2.143	PERLHOME - Location of PERL	288
A.2.144	SERVER_ROLES - Which Server Roles are Enabled.....	289
A.2.145	SERVER_ROLE_BATCH - Whether the Batch Server is Enabled in this Installation	289
A.2.146	SERVER_ROLE_INTEGRATION - Whether the IWS Server is Enabled in this Installation	289
A.2.147	SERVER_ROLE_ONLINE - Whether the Online Server is Enabled in this Installation	290
A.2.148	SOA_HOME - Location of Oracle SOA Suite	290
A.2.149	SOA_HOST - Hostname for Oracle SOA Suite	290
A.2.150	SOA_PORT_NUMBER - Port Number for Oracle SOA Suite	291
A.2.151	SPLADMIN - Administration UserID	291
A.2.152	SPLADMINGROUP - Administration Group	292
A.2.153	SPLApp - Name of Online WAR File.....	292
A.2.154	SPLDIR - Home Directory of Product.....	292
A.2.155	SPLDIROUT - Location of Product Output	293
A.2.156	SPLENVIRON - Environment Identifier	293
A.2.157	SPLSERVICEAPP - Name of Business Application Server Application.....	293
A.2.158	SPLWAS - J2EE Web Application Server Type	294
A.2.159	SPLWEBAPP – Name of Web Application Server Application.....	294
A.2.160	STRIP_HTML_COMMENTS - Strip Out Comments in Code	295
A.2.161	TIMEOUT - Mobile Connection Timeout.....	295
A.2.162	TOP_VERSION - Product Version.....	296
A.2.163	TOP_VERSION_NUM - High Level Product Version	296
A.2.164	TS_ALIAS - Trust Alias.....	296
A.2.165	TS_ALIAS_KEYALG - Key Algorithm	297
A.2.166	TS_ALIAS_KEYSIZE - Keysize	297
A.2.167	TS_HMAC_ALIAS - HMAC Key Alias.....	297
A.2.168	TS_HMAC_ALIAS_KEYALG - HMAC Key Algorithm.....	298
A.2.169	TS_HMAC_ALIAS_KEYSIZE - HMAC Keysize.....	298
A.2.170	TS_IMPORT_KEYSTORE_FOLDER - Import Folder for Trust Store.....	298
A.2.171	TS_KEYSTORE_FILE - Trust Store File Name	299
A.2.172	TS_MODE - Key Padding Mode	299
A.2.173	TS_PADDING - Key Padding Algorithm.....	299
A.2.174	TS_STOREPASS_FILE - Key Password Store Pass	300
A.2.175	TS_STORETYPE - Key Store Type	300
A.2.176	URL - Mobile JNDI URL	300
A.2.177	WAS_HOME - IBM WebSphere Home	301

A.2.178	WAS_PASSWORD - IBM WebSphere Administration Password	301
A.2.179	WAS_USERID - IBM WebSphere Administration User	302
A.2.180	WASND_DMGR_HOST - IBM WebSphere Deployment Manager Host Name.....	302
A.2.181	WASND_HOME - IBM WebSphere ND Home	303
A.2.182	WEBSERVICES_ENABLED - Whether Inbound Web Services is Enabled.....	303
A.2.183	WEB_ADDITIONAL_OPT - Additional Java Options for Web.....	304
A.2.184	WEB_APP - Name of WebSphere Server Application	304
A.2.185	WEB_APPVIEWER_FORM_LOGIN_ERROR_PAGE - AppViewer Form Login Error Page	304
A.2.186	WEB_APPVIEWER_FORM_LOGIN_PAGE - AppViewer Form Login Page	305
A.2.187	WEB_APPVIEWER_PRINCIPAL_NAME - Application Viewer Principal Name	305
A.2.188	WEB_APPVIEWER_ROLE_NAME - Application Viewer Security Role	305
A.2.189	WEB_BATCH_CLUSTER_URL - Batch Cluster URL	306
A.2.190	WEB_CONTEXT_ROOT - Web Context Root	306
A.2.191	WEB_DEPLOY_APPVIEWER – Deploy AppViewer or Not.....	306
A.2.192	WEB_DEPLOY_EAR - Deploy EAR File.....	307
A.2.193	WEB_ENABLE_HEALTHCHECK - Enable System Healthcheck	308
A.2.194	WEB_FORM_LOGIN_ERROR_PAGE - Default Form Login Error Page.....	308
A.2.195	WEB_FORM_LOGIN_PAGE - Default Form Login Page	309
A.2.196	WEB_HELP_FORM_LOGIN_ERROR_PAGE - Help Form Login Error Page	309
A.2.197	WEB_HELP_FORM_LOGIN_PAGE - Help Form Login Page	310
A.2.198	WEB_ISAPPVIEWER - Enable AppViewer	310
A.2.199	WEB_ISDEVELOPMENT - Development Environment	310
A.2.200	WEB_IWS_MDB_RUNAS_USER - Default User for MDB to Run as within Product	311
A.2.201	WEB_IWS_SUPER_USERS - Users to Run as in IWS	311
A.2.202	WEB_JMX_RMI_PORT_PERFORMANCE - JMX Port for Web Application Server Monitoring	312
A.2.203	WEB_L2_CACHE_MODE - Turn Off L2 Cache for Online Submission.....	312
A.2.204	WEB_MAXAGE - Text Cache.....	313
A.2.205	WEB_MAXAGEI - Image Cache.....	313
A.2.206	WEB_MEMORY_OPT_MAX - Maximum Web Application Server JVM Memory..	314
A.2.207	WEB_MEMORY_OPT_MAXPERMSIZE - Web Application Server JVM Max PermGen Size	314
A.2.208	WEB_MEMORY_OPT_MIN - Initial Web Application Server JVM Memory	315
A.2.209	WEB_NODENAME - IBM WebSphere ND Node Name	315
A.2.210	WEB_PRELOADALL - Preload All Pages on Startup	316
A.2.211	WEB_PRINCIPAL_NAME - Default J2EE Authorization Principal.....	316
A.2.212	WEB_ROLE_NAME - Default J2EE Authorization Role	317
A.2.213	WEB_SERVER_HOME - Location of Web Application Server	317
A.2.214	WEB_SERVER_VERSION - Web Server Version	318

A.2.215	WEB_SERVER_VERSION_MAIN	318
A.2.216	WEB_SPLPASS - Application Administration Password	319
A.2.217	WEB_SPLUSER - Application Administration UserID.....	319
A.2.218	WEB_SVRNAME - IBM WebSphere Server Name	320
A.2.219	WEB_WASPASS - IBM WebSphere JNDI Password	320
A.2.220	WEB_WASUSER - IBM WebSphere JNDI UserID	320
A.2.221	WEB_WLAUTHMETHOD - Authentication Method	321
A.2.222	WEB_WLHOST - Web Server Host	321
A.2.223	WEB_WLPAGECHECKSECONDS - Interval for Recompilation of JSP	322
A.2.224	WEB_WLPORT - Web Server HTTP Port.....	322
A.2.225	WEB_WLSSLPORT - Oracle WebLogic SSL HTTP Port.....	323
A.2.226	WEB_WLSYSPASS - Oracle WebLogic JNDI System Password.....	323
A.2.227	WEB_WLSYSUSER - Oracle WebLogic JNDI System UserID.....	324
A.2.228	WEB_WLS_SVRNAME - Oracle WebLogic Server Name	324
A.2.229	WLS_ADMIN_PORT - Admin Console Port Number.....	325
A.2.230	WLS_CLUSTER_NAME - Name of Cluster for Product.....	325
A.2.231	WLS_DIAGNOSTIC_BUILT_IN_MODULE - Diagnostic Module Name.....	325
A.2.232	WLS_DIAGNOSTIC_CONTEXT_ENABLED - ECID Support	326
A.2.233	WLS_DIAGNOSTIC_VOLUME- Diagnostic Volume	326
A.2.234	WLS_DOMAIN_HOME - Oracle WebLogic Domain Home	326
A.2.235	WLS_OVERRIDE_PROTECT - Override Protection	327
A.2.236	WLS_WEB_WLSYSPASS - Console Password for Oracle WebLogic.....	327
A.2.237	WLS_WEB_WLSYSUSER - Console User for Oracle WebLogic	328
A.2.238	WLTHININT3CLIENT_JAR_DIR - Loaction of Thin WebLogic T3 Client	328
A.2.239	WL_HOME - Oracle WebLogic Home	329
A.2.240	XAIApp - Name of XAI WAR File	329
A.2.241	XAI_DBPASS - Password for Database User for XAI	330
A.2.242	XAI_DBUSER - Database User Used for XAI.....	330
A.2.243	XQUERIES_TO_CACHE - Size of XQuery Cache.....	330
A.2.244	XQUERY_CACHE_FLUSH_TIMEOUT - Cache Life for XQueries.....	331
A.3	Web.xml 331	
A.3.1	Filter Mappings - J2EE Filters	332
A.3.2	disableCompression - Disable Compression	333
A.3.3	maxAge1 - Max Age for Images	333
A.3.4	maxAge - Max Age for Pages.....	334
A.3.5	auth-method - Authorization Method	335
A.3.6	fieldValuesAge - Server Cache Lifetime	336
A.3.7	disableUIPageCompression - Disable UI Compression	336
A.4	spl.properties.....	337

A.4.1	calendar.japanese.eras - Japanese Era Definition	337
A.4.2	com.oracle.ouaf.allowed.file.locations – XML File with Substitution Variable Definitions	338
A.4.3	com.oracle.ouaf.customer.whitelist.file – Customer’s URL Whitelist File.....	338
A.4.4	com.oracle.ouaf.fileParamValidation.enable – File Parameter Validation.....	338
A.4.5	com.oracle.ouaf.migrationAssistant.exportDirectory – Directory for Exported CMA File	339
A.4.6	com.oracle.ouaf.migrationAssistant.importDirectory – Directory for CMA File for Import	339
A.4.7	com.oracle.ouaf.migrationAssistant.fileExtension – Extension of CMA File	340
A.4.8	com.oracle.ouaf.system.database.disableTagging - Disables Database Tagging .	340
A.4.9	com.oracle.ouaf.system.keystore.alias - Keystore Alias.....	340
A.4.10	com.oracle.ouaf.system.keystore.hmac_key_alias - HMAC Alias	341
A.4.11	com.oracle.ouaf.system.keystore.file - Location of Keystore.....	341
A.4.12	com.oracle.ouaf.system.keystore.mode - Keystore Mode.....	342
A.4.13	com.oracle.ouaf.system.keystore.padding - Key Padding	342
A.4.14	com.oracle.ouaf.system.keystore.passwordFileName - Password File	343
A.4.15	com.oracle.ouaf.system.keystore.type - Keystore Type.....	343
A.4.16	com.oracle.ouaf.system.truststore.file - Location of Truststore	344
A.4.17	com.oracle.ouaf.system.truststore.passwordFileName - Location of Truststore Password file	344
A.4.18	com.oracle.ouaf.truststore.type - Type of Truststore	344
A.4.19	com.oracle.ouaf.urlValidator.enable – Enable Restriction of URLs.....	345
A.4.20	com.oracle.ouaf.whitelist.file – Oracle URL Whitelist Filename and Location.....	345
A.4.21	com.oracle.ouaf.xsd.dir - Location of XSD Files for XAI	345
A.4.22	com.oracle.ouaf.xsl.dir - Location of XSL Files for XAI	346
A.4.23	com.oracle.XPath.LRUSize - XPath Cache	346
A.4.24	com.oracle.XPath.flushTimeout - XPath Flush.....	346
A.4.25	com.splwg.batch.cluster.jvmName - Online Batch JVM Name	347
A.4.26	com.splwg.batch.scheduler.daemon - Online Submission Daemon	347
A.4.27	com.splwg.grid.executionMode - Online Execution Mode.....	347
A.4.28	com.splwg.grid.online.enabled - Online Batch Server.....	348
A.4.29	com.splwg.grid.distThreadPool.threads.DEFAULT - Online Submission Threadpool	348
A.4.30	com.splwg.schema.newValidations.F1 - Set Behavior of Validations.....	349
A.4.31	jmx.remote.x.access.file - JMX Access Control	349
A.4.32	jmx.remote.x.password.file - JMX Password Control	350
A.4.33	oracle.ouaf.jmx.remote.startPort - JMX Override Port	350
A.4.34	ouaf.accessiblity.features - Enable Accessibility Features	351
A.4.35	ouaf.attachment.disableSpecialCharCheckOnFileName - Disable Special Characters on File Name	351

A.4.36	ouaf.batch.onlineLogDir - Online Line Batch Log Directory.....	352
A.4.37	ouaf.batch.onlineLogDir.retain – Retain Online Line Batch Log Files	352
A.4.38	ouaf.database.session.setInstallationTimeZone - Set Time Zone for Sessions	352
A.4.39	ouaf.flush.jms.disabled - Global Flush supported.....	353
A.4.40	ouaf.flush.jms.connection - Connection Factory for Global Flush.....	353
A.4.41	ouaf.flush.jms.requestTopic - Global Flush Request Topic.....	354
A.4.42	ouaf.flush.jms.responseTopic - Global Flush Response Topic	354
A.4.43	ouaf.runtime.compatibility.enablePrecisionScaleOnMoney - Money Processing	354
A.4.44	ouaf.jmx.com.oracle.ouaf.ws.mbeans.WSFlushBean - WS Cache Flush	355
A.4.45	ouaf.jmx.com.splwg.base.support.management.mbe-an.JVMInfo - JVM Information	356
A.4.46	ouaf.jmx.com.splwg.base.web.mbeans.FlushBean - Manage Cache	356
A.4.47	ouaf.list.buffer.limit - List Iteration limit.....	357
A.4.48	ouaf.messaging.transformerfactory - Transformer	357
A.4.49	ouaf.shortcut.ignore.altKeys - Disable Hot Keys.....	357
A.4.50	ouaf.timeout.business_object.default - Set Default Business Object Timeout	358
A.4.51	ouaf.timeout.business_object.<bocode> - Set Specific Business Object Timeout	358
A.4.52	ouaf.timeout.business_service.default - Set Default Business Service Timeout..	359
A.4.53	ouaf.timeout.business_service.<bscode> - Set Specific Business Service Timeout	359
A.4.54	ouaf.timeout.query.default - Set Default Query Timeout	360
A.4.55	ouaf.timeout.query.<zonecode> - Set Specific Query Timeout.....	360
A.4.56	ouaf.timeout.script.default - Set Default Script Timeout	361
A.4.57	ouaf.timeout.script.<scriptname> - Set Specific Script Timeout	361
A.4.58	ouaf.timeout.service.default - Set Default Service Timeout	362
A.4.59	ouaf.timeout.service.<service> - Set Specific Service Timeout	362
A.4.60	ouaf.web.appViewer.coreAppURL - AppViewer Callback URL	363
A.4.61	ouaf.web.disablePreload - Disable Screen Preload	363
A.4.62	ouaf.web.help.coreAppURL - Help Callback URL	364
A.4.63	ouaf.web.helpRootURL - Help URL	364
A.4.64	ouaf.web.JspHeader.maxAge - JSP Age	365
A.4.65	ouaf.web.preloadAllPages - Preload Scope	365
A.4.66	ouaf.web.useOHW - Use Oracle Help for Web Engine	366
A.4.67	ouaf.weblogic.enableDiagnostics - Enable ECID Tracking	366
A.4.68	ouaf.webservices.security.defaultPolicy – IWS Customized Security Policy	366
A.4.69	ouaf.ws.defaultUser - Default User for Web Services	367
A.4.70	ouaf.ws.deploy.appxml.file - Application XML File for Inbound Web Services	367
A.4.71	ouaf.ws.deploy.ear - EAR File Name for Inbound Web Services	367
A.4.72	ouaf.ws.deploy.contextpath - Context Path for Inbound Web Services	368
A.4.73	ouaf.ws.deploy.user - Web Services Deployment User.....	368

A.4.74	ouaf.ws.pageService.annotations - Security Annotation for XAI Legacy services	369
A.4.75	ouaf.ws.superusers - Effective Web Services Users	369
A.4.76	ouaf.ws.tools.artifact.generated.buildfile - Build File.....	370
A.4.77	ouaf.ws.tools.artifact.generated.sourcedir - Location of Generated Source	370
A.4.78	ouaf.ws.tools.artifact.resource.dir - Location of 319 Resources	371
A.4.79	ouaf.ws.tools.artifact.schema.dir - Location of Schemas	371
A.4.80	ouaf.ws.tools.artifact.xsl.dir - Web Service XSL Location	372
A.4.81	ouaf.ws.tracing - Inbound Web Services Tracing.....	372
A.4.82	ouaf.ws.xslDirOverride - Override XSL Location	373
A.4.83	ouaf.xai.HTTPBasicAuthPasswordEnc - Default XAI Password	373
A.4.84	ouaf.xai.HTTPBasicAuthUser - Default XAI User	373
A.4.85	ouaf.xai.XAIserverURL - Default XAI URL	374
A.4.86	spl.csv.delimiter.useFromDisplayProfile - List CSV Delimeter	374
A.4.87	spl.ejbContainer.contextFactory - Context Factory for Business Application Server	375
A.4.88	spl.ejbContainer.password - Password for Business Application Server.....	375
A.4.89	spl.ejbContainer.url - Business Application Server URL.....	376
A.4.90	spl.ejbContainer.user - Business Application Server User	376
A.4.91	spl.geocodeDatasource.contextFactory - GIS Context Factory.....	377
A.4.92	spl.geocodeDatasource.password - GIS Connection Password	377
A.4.93	spl.geocodeDatasource.url - GIS Data Source	378
A.4.94	spl.geocodeDatasource.user - GIS Connection User.....	378
A.4.95	spl.mwm.abr.contextFactory - ABR Context Factory.....	379
A.4.96	spl.mwm.abr.password - ABR Connection Password	379
A.4.97	spl.mwm.abr.timeout - Timeout for ABR.....	380
A.4.98	spl.mwm.abr.url - ABR URL.....	380
A.4.99	spl.mwm.abr.userid - ABR Connection User.....	381
A.4.100	spl.mwm.scheduler.abr.maxProcessingTime - Processing Time for ABR	381
A.4.101	spl.mwm.scheduler.abr.minRequests - Initial Scheduler Pool Size	381
A.4.102	spl.mwm.scheduler.cleanse.interval - Scheduler Cache Clense	382
A.4.103	spl.mwm.scheduler.connectionTimeout - Scheduler Connection Timeout	382
A.4.104	spl.mwm.scheduler.maintenanceCycleTime - Scheduler Integrity Check	382
A.4.105	spl.mwm.scheduler.mapDir - Map Directory.....	383
A.4.106	spl.mwm.scheduler.nodeId - Scheduler Node	383
A.4.107	spl.runtime.mwm.scheduler.ipcStartPort - IPC Start Port.....	383
A.4.108	spl.runtime.compatibility.uiMapDisableInputValue - Map Defaults	384
A.4.109	spl.runtime.compatibility.uiMapDropdownSelectFirstValue - Dropdown Defaults	384
A.4.110	spl.runtime.compatibility.uiMapDisableTitle - Screen Title Defaults	385

A.4.111	spl.runtime.compatibility.uiMapDisableGenerateUniqueHtmlIDs - Map IDs	385
A.4.112	spl.runtime.disableCSRFProtection - Disable Security Tokens	386
A.4.113	spl.runtime.environ.init.dir - Location of Configuration Files.....	386
A.4.114	spl.runtime.environ.isWebExpanded - Expanded Mode	387
A.4.115	spl.runtime.environ.SPLEBASE - Location of Software	387
A.4.116	spl.runtime.initiatize.waittime - Start Time Delay.....	388
A.4.117	spl.runtime.environ.SPLOUTPUT - Location of Output.....	388
A.4.118	spl.runtime.management.batch.cluster.url - Batch Cluster URL	388
A.4.119	spl.runtime.management.connector.url.default - JMX URL.....	389
A.4.120	spl.runtime.management.rmi.port - JMX Port	389
A.4.121	spl.runtime.options.isFCFEnabled - RAC FCF Enabled	390
A.4.122	spl.runtime.options.onsserver=nodes - ONS Configuration	390
A.4.123	spl.runtime.options.allowSystemDateOverride - Set Testing Date	391
A.4.124	spl.runtime.options.createSimpleWebAppContextEnable - Web Cache Loading	391
A.4.125	spl.runtime.options.isDevelopmentMode - Development Mode	392
A.4.126	spl.runtime.oracle.statementCacheSize - Java SQL Cache Size	393
A.4.127	spl.runtime.performSignedNumberValidation.<product> - Number Validation..	393
A.4.128	spl.runtime.service.extraInstallationServices - Installation Service	394
A.4.129	spl.runtime.sql.highValue - SQL High Value.....	395
A.4.130	spl.runtime.utf8Database - UTF8 Support	395
A.4.131	spl.serviceBean.jndi.name - JNDI Name for Business Application Server	395
A.4.132	spl.tools.loaded.applications - Loaded Product.....	396
A.5	hibernate.properties	396
A.5.1	hibernate.cache.use_second_level_cache - Use Cache.....	396
A.5.2	hibernate.connection.datasource - JNDI Data Source.....	397
A.5.3	hibernate.connection.driver_class - Connection Driver Class	397
A.5.4	hibernate.connection.password - Database User Password	398
A.5.5	hibernate.connection.provider_class - Connection Provider	398
A.5.6	hibernate.connection.release_mode - Connection Release.....	399
A.5.7	hibernate.connection.url - JDBC URL.....	399
A.5.8	hibernate.connection.username - Database User	400
A.5.9	hibernate.dialect - Dialect Used.....	400
A.5.10	hibernate.jdbc.batch_size - JDBC2 Update Support	401
A.5.11	hibernate.jdbc.fetch_size - Solution Set Size	401
A.5.12	hibernate.max_fetch_depth - Join Fetch Depth.....	402
A.5.13	hibernate.query.factory_class - HQL Parser	402
A.5.14	hibernate.query.substitutions - Literal Mappings	403
A.5.15	hibernate.show_sql - Debug Mode.....	403
A.5.16	hibernate.transaction.factory_class - Transaction Class	404

A.5.17	hibernate.ucp.connection_wait_timeout - UCP Connection Timeout	404
A.5.18	hibernate.ucp.inactive_connection_timeout - Connection Inactivity Timeout....	405
A.5.19	hibernate.ucp.jmx_enabled - Enable UCP JMX.....	405
A.5.20	hibernate.ucp.max_size - Maximum Pool Size	406
A.5.21	hibernate.ucp.max_statements - SQL Buffer Size	406
A.5.22	hibernate.ucp.min_size - Minimum Pool Size.....	407
A.6	submitbatch.properties.....	408
A.6.1	com.oracle.ouaf.system.keystore.alias - KeyStore Alias.....	408
A.6.2	com.oracle.ouaf.system.keystore.file - KeyStore File	408
A.6.3	com.oracle.ouaf.system.keystore.hmac_key_alias - KeyStore Mode	409
A.6.4	com.oracle.ouaf.system.keystore.mode - KeyStore Mode	409
A.6.5	com.oracle.ouaf.system.keystore.padding - KeyStore Padding Algorithm	410
A.6.6	com.oracle.ouaf.system.keystore.passwordFileName - KeyStore File.....	410
A.6.7	com.oracle.ouaf.system.keystore.type - KeyStore Type	411
A.6.8	com.ouaf.batch.jvmoptions - JVM Options	411
A.6.9	com.splwg.grid.executionMode - Mode of Execution.....	412
A.6.10	com.splwg.batch.submitter - THIN Submitter	412
A.6.11	com.splwg.batch.submitter.batchCd - Batch Code	413
A.6.12	com.splwg.batch.submitter.distThreadPool - Threadpool	413
A.6.13	com.splwg.batch.submitter.languageCd - Language Code.....	414
A.6.14	com.splwg.batch.submitter.maximumCommitRecords - Commit Interval	414
A.6.15	com.splwg.batch.submitter.promptForValues - Prompt for Values.....	415
A.6.16	com.splwg.batch.submitter.processDate - Business Date.....	415
A.6.17	com.splwg.batch.submitter.rerunNumber - Re Run Number	416
A.6.18	com.splwg.batch.submitter.softParameter - Job Parameters.....	417
A.6.19	com.splwg.batch.submitter.threadCount - Thread Limit	418
A.6.20	com.splwg.batch.submitter.threadNumber - Thread Number	418
A.6.21	com.splwg.batch.submitter.traceProgramEnd - Trace Program End	419
A.6.22	com.splwg.batch.submitter.traceProgramStart - Trace Program Start.....	419
A.6.23	com.splwg.batch.submitter.traceSQL - Trace SQL Statements	420
A.6.24	com.splwg.batch.submitter.traceStandardOut - Trace Output Statements	420
A.6.25	com.splwg.batch.submitter.userId - Security User.....	421
A.6.26	spl.runtime.batch.L2CacheMode - L2 Cache Control	422
A.6.27	tangosol.coherence.distributed.localstorage - Cache Mode.....	423
A.6.28	tangosol.coherence.role - Submitter Role	423
A.7	threadpoolworker.properties.....	424
A.7.1	com.oracle.ouaf.batch.scriptDir - Base Scripts Directory for Infrastructure Job..	424
A.7.2	com.oracle.ouaf.system.keystore.alias - Threadpoolworker KeyStore Alias.....	424
A.7.3	com.oracle.ouaf.system.keystore.file - Threadpoolworker KeyStore File.....	425

A.7.4	com.oracle.ouaf.system.keystore.hmac_key_alias - Threadpoolworker KeyStore HMAC Key Alias	426
A.7.5	com.oracle.ouaf.system.keystore.mode - Threadpoolworker KeyStore Mode ...	426
A.7.6	com.oracle.ouaf.system.keystore.padding - Threadpoolworker KeyStore Padding Algorithm	427
A.7.7	com.oracle.ouaf.system.keystore.passwordFileName - Threadpoolworker KeyStore File	427
A.7.8	com.oracle.ouaf.system.keystore.type - Threadpoolworker KeyStore Type	428
A.7.9	com.ouaf.batch.disableAutoFlush – Auto Flush Batch L2 Cache	428
A.7.10	com.ouaf.batch.flushIntervalInSeconds – Batch L2 Cache Auto Flush Interval....	428
A.7.11	com.ouaf.batch.jvmoptions - Threadpool JVM Options	429
A.7.12	com.splwg.grid.executionMode - Threadpool Mode of Execution	430
A.7.13	com.splwg.grid.distThreadPool.threads - Threadpool Thread Limit	430
A.7.14	com.splwg.batch.scheduler.daemon - Scheduler Daemon	431
A.7.15	oracle.ouaf.jmx.remote.maxPortsToTry - Ports to Attempt to Connect to.....	432
A.7.16	oracle.ouaf.jmx.remote.startPort - Override Batch JMX Port	432
A.7.17	ouaf.batch.onlineLogDir - Online Line Batch Log Directory.....	433
A.7.18	ouaf.batch.onlineLogDir.retain – Retain Online Line Batch Log Files	433
A.7.19	spl.runtime.batch.disableDeferredKeyInserts - Deferred Key Inserts	433
A.7.20	spl.runtime.batch.L2CacheMode - Threadpoolworker L2 Cache Control	434
A.7.21	spl.runtime.management.connector.url.default - Batch JMX URL.....	435
A.7.22	spl.runtime.management.rmi.port - Batch JMX Port	435
A.7.23	tangosol.coherence.distributed.localstorage - DistributedCache Storage	436
A.7.24	tangosol.coherence.distributed.threads - Internal Cache Threads	436
A.7.25	tangosol.coherence.invocation.threads - Internal Invocation Threads.....	437
A.7.26	tangosol.coherence.localhost - Unicast Host Address.....	437
A.7.27	tangosol.coherence.localport - Unicast Port	438
A.7.28	tangosol.coherence.localport.adjust - Unicast Port Adjustment.....	438
A.7.29	tangosol.coherence.role - Threadpoolworker Role	439
A.8	coherence-cache.config.xml.....	439
A.9	tangosol-coherence-override.xml	439

1. Architecture

The product is a multi-layered product with distinct tiers. The figure below illustrates the architecture of the product:




Figure 1: Product Architecture

The components of the architecture are as follows:

- **Browser Client** – The client component is a browser based interface which is light and only requires the Internet Explorer browser to operate.
- Communication between the client and server uses the HTTPS protocol across a TCP/IP network. Non communications (HTTP) is also supported. The user simply uses a URL containing the product hostname and allocated port number in the address bar of Internet Explorer to access the application.

Note:

It is possible to use proxies to hide or translate the hostname and port numbers. Refer to the documentation provided with your J2EE Web application server documentation for proxy support instructions.

By default SSL is enabled with minimal facilities, by default for all new installations. Refer to the SSL documentation provided with your J2EE Server to enable SSL to your individual needs.

The default SSL certificate provided by Oracle is recommended for demonstration and development purposes only. It is highly recommended that customers purchase their own certificates for use for SSL.

- **Mobile Device Terminal (MDT)/Mobile Interface** – In some products the Mobile framework is deployed to allow mobile devices to interact with server processes. Refer to the product guides for applicability of the mobile framework to your product. **MOB**

Note: This manual has minimal information about the operation of the Mobile component of the Oracle Utilities Application Framework.

- **Web Application Server (WAS)** – The product web application is housed in a J2EE compliant Web application server (Refer to the **Supported Platforms** section of the *Oracle Revenue Management and Billing Installation Guide* for J2EE Web application servers and versions supported) This server can be run on a variety of supported Windows, Linux and UNIX platforms (Refer to the Supported Platforms section of the *Oracle Revenue Management and Billing Installation Guide* for operating systems and versions supported). Within the Web application server the pages for the product are rendered using a combination of metadata and formatting rules to ensure a consistent look and feel. These pages are written using a combination of J2EE Java script and Java. These pages are cached on the Web Server and served to the client upon request. If the page requires business rules to be invoked then business objects are called from this server.
- **Business Application Server (BAS)** – The business component of the architecture can be installed as part of the Web application server (default) or as a separate component. This means the Business Application Server is also housed in a J2EE compliant Web application server (Refer to the Supported Platforms section of the *Oracle Revenue Management and Billing Installation Guide* for J2EE Web application servers and versions supported). This server can be run on a variety of supported Windows, Linux and UNIX platforms (Refer to the Supported Platforms section of the *Oracle Revenue Management and Billing Installation Guide* for operating systems and versions supported). Within the Business Application Server the following components are implemented:
 - **Business Objects** – The business logic for each object in the system is expressed as a Java object. It contains all the SQL, programmatic rules and structures to manage the data for the transactions. In some products.
 - **DB Connection Pool** – If any database access is required, we use an industry component called Universal Connection Pool to manage and pool the connections to the database for the batch component and use the Web Server's own native JDBC connection pooling for the online and Web Services component. This will reserve connections and ensure efficient use of connections to the database. To access the database product uses the networking client provided by the DBMS vendors to ensure correct connection. For example, Oracle provides SQL*NET, DB2 provides UDB Connect and SQL Server uses .NET drivers. These clients are multi-protocol for maximum flexibility.
- **Database Server** – The RDBMS used for the implementation is implemented in the database server. The product supports a number of databases (Refer to the **Supported Platforms** section of the *Oracle Revenue Management and Billing Installation Guide* for databases and versions supported). The database server only stores and retrieves the data for the product as all the business logic is in the business objects.

- **Batch Server** - In some cases, processes need to be processed in bulk and in the background. The Batch Server is a set of JVM's clustered using Oracle Coherence².
This feature supports multi-threaded background processes processing records in bulk across a cluster¹ **BATCH**.

1.1 Roles and Features

Each tier in the architecture has a specific role in the operation of the product. The sections below outline the roles and features of each tier.

1.1.1 Client

The Browser User interface (BUI) is a combination of HTML and Java-script. AJAX, shorthand for Asynchronous JavaScript and XML, is a Web development technique for creating interactive Web applications. This makes web pages more responsive by exchanging small amounts of data with the server, so that the entire page does not have to be reloaded each time the user makes a change. This increases the Web page's interactivity, speed, and usability.

Note:

Refer to the *Oracle Revenue Management and Billing Installation Guide* for the supported browsers and the supported versions of those browsers.

In past releases, Adobe/Apache Flash Player was required for displaying and interacting with graphs. This is no longer required.

There are no ActiveX or Java components in the base product installation. This means that the deployment of the browser client is relatively simple as the only required component to use the product is a supported version of Internet Explorer on the client machine. If the implementation requires ActiveX controls for extensions then they can be added and used for the implementation.

The Browser tier of the product is provided for the end users to access the product on a desktop. The client provides the following roles in the architecture:

- **Screen Rendering and Caching** – All the screens are rendered using standard HTML and JavaScript (not Java). The rendering is performed as the screen is served from the Web Application server and stored in the local browser cache.
- **User Interaction** – The client provides the user with the screen interaction. After page is rendered the user can interact (manipulate data and screen elements) as per their business transaction. The browser client is responsible for ensuring that users can navigate and interact with the screen elements (e.g. resizing, display correctly).
- **User Context** – The product is stateless and therefore the client stores the transactional context locally and passes this to the transaction as required. The client records the context of the transaction in the browser memory.

No business logic is stored on the client component.

¹ The Oracle Coherence implementation is embedded with the product and is restricted to the background processing component only. Implementation of other Oracle Coherence features beyond that provided with the integration requires the purchase of a full Oracle Coherence license.

1.1.2 Web Application Server

The product is a J2EE set of Web applications that are housed in a J2EE compliant Web application server. The product and the Web application server provide the following roles in the architecture:

- **Authentication** – The Web application server software that houses the product provides adapters to common security repositories. This means that security products interfaced to the Web application server software can be used in conjunction (with configuration) with the product.
- **Managing Client connections** – The Web application server software manages any client connections (during and after they are authenticated) for processing and availability.
- **Page Server** – The major responsibility of the Web application server is to serve pages to the client on demand. At start-up time (or at the first request for a particular page) the product generates the screens dynamically using metadata and rendering style sheets. These are cached for reuse locally.
- **Cache Management** – For performance reasons, the static data (usually metadata and configuration data) is cached in memory on the Web application server.

No business logic is stored on the Web application server component. The Web application server Component of the product is written in Java and JavaScript.

1.1.3 Business Application Server

The product is a J2EE set of business applications that are housed in a J2EE compliant Web application server (this can be the same instance of the Web application server or a separate one). The product and the Business Application Server provide the following roles in the architecture:

- **Authorization** – After authentication has been performed by the Web application server, the Business Application server is responsible for determining which functions and which data can be accessed.
- **Data Integrity** – The Business Application Server contains the business logic to maintain referential integrity for the product data.
- **Validation** – The Business Application Server contains the business logic that contains all the validation rules for the product data.
- **Business Rules** – The Business Application Server contains the business logic that implements business rules and performs calculations.
- **SQL** – The Business Application Server contains all the SQL statements and formats and processes results from those SQL statements.

The Business Application Server Component of the product is written in Java.

1.1.4 Database Server

The product contains a database schema within a database management system. The database server has the following roles in the architecture:

- **Data Storage** – The database is responsible for efficiently storing all data.
- **Data Retrieval** – The database is responsible for efficiently retrieving data using SQL provided by the Business Application Server.

- **Data Management** – The database is responsible for efficiently managing all data.

No business logic is stored on the Database Server.

Note: Refer to the DBA Guide for your product for specific facilities supported by the Database Server.

1.1.5 Batch Server **BATCH**

The product is known for its online (or foreground) processing (a.k.a. online processing) but one of the major features of the product is its set of background processes. Background processing is a major part of the product with numerous background processes supplied as standard.

The easiest way to understand the concept behind background processing is to think that background processing is like a super efficient user that operates on a batch of objects. That is why background processing is commonly called Batch.

Note: For publishing purpose the term batch may also be used to denote background processing in this document.

Online typically operates on one object at a time, initiated by an online user or a Web Service call, where batch can operate on one or more objects (also known as a set of objects) at a time, initiated using a number of technologies.




Figure 2: Batch Processing Architecture

The main reasoning behind the super efficient user is that each background process consists of a driver object that identifies the set of valid objects to process and then processes each object through the same business objects that the online uses. For example, the BILLING driver determines which accounts are eligible to be billed according to business calendar and then passes each account to the rate object

to produce a bill. Contrast this with online bill generation, where the user identifies the account manually, and then that single account is passed to the same rate object to be billed. The background process can call more than one object during the duration of the background process.

For the batch process, all of the database access and object access (including access to business objects, algorithms, user exits (server side only) etc is done through the Oracle Utilities Application Framework.

1.1.5.1 Background Processing and the Architecture BATCH

The Background Processing component is run within the Oracle Utilities Application Framework and is associated typically with the Business Application Server. It is not associated with the Web Application Server and does not require the Web Application Server to be active to operate. The only component other than product that the background processing component requires is the database server (or tier).

Depending on the initiation method employed the background processing component uses a standalone copy of the product to perform access to the database and business objects and its own copy of the same business objects used by the Business Application Server.

Essentially the background processing has its own resources (Java Virtual machines (JVMs), connection pools) independent of the rest of the architecture and can therefore be run on the same hardware as the rest of the architecture or on dedicated hardware.

1.1.5.2 Batch Architecture Overview BATCH

The background processing component of the architecture is a scalable clustered batch approach that allows implementation, using configuration, to spread the batch load across a clustered based architecture.




Figure 3: Batch Architecture Overview

The architecture has the following features:

- A background process cluster is defined using the inbuilt Oracle Coherence² configuration. This cluster defines the group of hosts, either communicating via unicast or multicast, which will execute background processing threads.
- Within the cluster, the configuration defines threadpoolworkers (also known as workers). These are running Java Virtual machines where the batch processes are executed. Threadpoolworkers are named to segregate batch threads and can be clustered across hosts defined in the Coherence cluster. Threadpoolworkers are defined with a maximum limit on the number of threads supported per instance of the threadpool.
- Background processes are submitted (known as submitters) to the named threadpools either at a particular threadpool/host instance or automatically distributed across a threadpool across the cluster.
- A background process is defined within the meta data as a Batch Control which defines the physical characteristics of the job as well as any configurable parameters of the background process.

² The Oracle Coherence implementation within the product uses a subset of the Oracle Coherence feature set, specifically Named (or Job) Caches.

- When a background process is executed, a number of threads (1 to many) are specified in the execution. Each thread will create Batch Instance records to track the progress of the job internally (exposed via the Batch Run Tree transaction within the product).
- Oracle Coherence is used, internally, to manage the communication between the cluster and all the members (such as workers and submitters) within that cluster. If a submitter or workers completes the thread or aborts then the cluster is informed and synchronized to take this into account. For instance, in the case of a status change (Completion or abort) the Batch Instance record is updated to reflect the state of the job.

2. Concepts

Before you attempt to configure or operate the product, there are important concepts that you should understand. These concepts are addressed in this document as a basis for the other documents in the technical documentation.

2.1 Environment

In a product implementation and post-implementation there will be a number of copies of the product installed. Each copy of the product is known as an environment. Each environment will be created for a specific purpose, according to your site plans, and accessible to a group of users deemed necessary for that purpose. For example, there will be at least one testing environment where designated personnel will perform their testing tasks.

For planning purposes, an environment is an instance of:

- The Web applications deployed in a J2EE Web application server. This may be in a single server or across a cluster of servers.
- The business applications deployed in a J2EE Web application server. This can be the same physical J2EE Web application server or another instance (such as a separate server). This may be in a single server or across a cluster of servers.
- A database containing the product schema. Physically, a schema can exist in an individual database instance or shared within a database instance (i.e. you can install multiple schemas of the product in the same database). This may be in a single server or across a cluster of servers.

While there is no restriction on the number of environments it is recommended that the minimal number of copies of the product is installed using the guidelines outlined in the *Environment Management document* in the Software Configuration Management Series (Doc ID: 560401.1) on [My Oracle Support](#).

2.1.1 Environment Identifier

As part of an installation an environment identifier is generated for the installation. This identifier is used by the technical utilities to manage the components and servers across the architecture. The environment identifier is used in the following ways:

- The Oracle Application Management Pack for Oracle Utilities uses the environment identifier to link child targets to an Utilities Environment target. This is used for monitoring and managing disparate targets (within a single host or across multiple hosts).
- It is used for tracking purposes only outside of the Oracle Application Management Pack for Oracle Utilities.

This feature is used in conjunction with the Server Roles facility.

2.1.2 Server Roles

One of the features of the installation and configuration is the ability to design architecture roles to a single installation (i.e. a product home). This allows the product to support specific roles per installation or a combination of roles for a single installation for flexibility. There are three roles available to be used:

Role	Usage
batch	This installation will use the batch server functionality
integration	This installation will use the webservice functionality
online	This installation will use the online functionality

Selection of each of the roles will enable or disable certain parameters that are available in the configureEnv[.sh] utility.

Note:

Even though the role can be set for individual sets of functionality, all the code and facilities are installed and patched to support post installation role change.

If the role is changed post installation additional parameters may need to be provided.

Once the role is set a number of additional configuration parameters are set in the ENVIRON.INI:

- SERVER_ROLE_BATCH
- SERVER_ROLE_INTEGRATION
- SERVER_ROLE_ONLINE

2.2 Administration User ID and Group

Prior to installing the product, you create a UNIX administration User ID and administration group. This account is used to install and operate the product. The product administration User ID and product group is provided as a parameter during the installation process. By default, the product administration user ID is splsys (SPLADMIN parameter and environment variable) and the group is splusr (SPLADMINGRP parameter and environment variable). However, alternative values can be used according to your site standards.

The administration User ID is responsible for the following:

- It is the owner of the majority of the files installed for the product.
- It is the only User ID that should be used to run any of the administration tools provided with the product.
- It is the User ID that owns the UNIX resources used by the product. When the product is running, this User ID owns the processes associated with running the base software. The administration User ID should be protected from unauthorized use. If components of the responsibility of administration need to be delegated to other users on the machine, we recommend not giving out the administration User ID. Instead, an alternative solution may be sought (such as using sudo or similar security tools).

The administration User ID should not be used for any of the following:

- As a product end user. By default, the administration User ID does not have access to the functionality of the product.
- To run product background processes.
- To manipulate data files exported from or imported into the product from any interfaces.

This technical document will refer to the administration User ID as `splsys`. If your site uses an alternative User ID as the administration User ID, substitute that User ID value for `splsys`.

Implementation Tip: It is possible to implement a different owner per environment in the product. Why would you want to do this? If you want to allow developers or testers to restart environments themselves, you can give access only to appropriate environments to distribute the administration. This can be achieved by installing the product with different User IDs. You must log in and administrate each environment with its account only.

2.3 Native Support VS Embedded Support

Note:

This facility applies to Oracle WebLogic customers only. IBM WebSphere uses Native Support only.

This section only applies to the online and Web Services capabilities of the architecture.

Native mode installation is recommended for Production environments and non-development environments.

Embedded mode installation is recommended for development or demonstration environments.

By default, the utilities and configuration files use Oracle WebLogic in embedded mode. In this mode the Oracle WebLogic installation does not house the deployment of the product within the Oracle WebLogic installation structure. The utilities and configuration files allow the Oracle WebLogic installation to logically reference the structures and deployment files from the `splapp` directory within the product installation. The process uses templates to create product configuration files as well as Oracle WebLogic configuration files and utilities to logically reference the files in the product structure.

This has advantages where a single installation of Oracle WebLogic can be used for multiple product environments (including development environments and different products on the same framework) and is therefore ideal for non-production environments.

Whilst the embedded environment is recommended for non-production environment it has limitations that are not practical for a production environment. These limitations are:

- **Clustering Support** – By default the installation and creation of the configuration files predefines a simple installation with a single server. In production Oracle WebLogic clustering is typically used and this is difficult to configure and maintain when using embedded mode, without manual manipulation of configuration files.
- **Administration Server installation** – In each installation of the product the administration console is deployed in each server which is not recommended for production environments. Typically, a single installation of the administration server will exist, or Oracle Enterprise Manager will be used, for production management of the environment.

- **Set configuration** – The product installation contains a set configuration which is a common installation for non-production environments and is not optimized for production.

It is possible to use the native mode of Oracle WebLogic to house the product. In this case, the product is installed as outlined in the *Oracle Revenue Management and Billing Installation Guide* but deployed to the Oracle WebLogic domain location using the Oracle WebLogic deployment tools and managed from the console. This allows the native tools to be used instead of the provided utilities and allows for the console to be used to manage the product. In this mode the product runtime for the product is either embedded in the EAR files or referenced indirectly by the EAR file.

The figures below illustrate the architecture differences in the two approaches:




Figure 4: Native and Embedded Architectures

In the embedded approach the domain files exist under the product installation and are built and maintained using the `configureEnv` and `initialSetup` utilities. No product installation files exist in the Oracle WebLogic installation but the Oracle WebLogic runtime is used by the generated utilities. Hence the term, embedded mode. This is recommended for non-production environments as it minimizes the number of Oracle WebLogic installations.

In the native approach, the domain files exist under the Oracle WebLogic installation location, as other Oracle applications use. The product files are deployed to the Oracle WebLogic location using the

deployment utilities provided by Oracle WebLogic (console or WLST can be used). This means that all the administration for any Oracle WebLogic configuration can be performed from the console rather than from command lines and configuration files. This approach is recommended for customers using Oracle ExaLogic and/or Oracle WebLogic clustering.

In both modes all the product specific configuration files are maintained using the facilities outlined in this manual. Refer to the *Oracle Revenue Management and Billing Installation Guide* for steps to setup embedded or native mode.

Note: For native installation instructions, refer to *Native Installation Oracle Utilities Application Framework (Doc ID: 1544969.1)* available on [My Oracle Support](#) and Oracle Revenue Management and Billing Installation Guide.

This guide will outline the operations and configuration for both approaches.

2.4 Directory Structure

In an effort to facilitate upgrades and ease maintenance, the product installation process creates a very specific directory hierarchy under the administration user ID of splsys (by default). The structure holds all the code, system products, scripts and temporary files that are created by the product during installation and operation.

Note:

Every part of the product relies on the fact that this directory structure and the files within remain intact as delivered.

At no time should you modify any of the supplied programs or scripts without the express direction of Oracle.

There are two different directory structures that the product application uses:

- Base code directory structure (denoted in this documentation as <SPDIR>)
- Application output directory structure / log directory (denoted in this documentation as <SPDIROUT>)

Within each of the structures, there is a mount point and a subdirectory for each environment <environment> installed on the machine. The base mount point <SPDIR> contains the environment directories that hold all of the application software for each particular environment. The application output mount point <SPDIROUT> contains the environment directories that hold temporary files (such as the output batch) as well as batch log files. The default <SPDIR> directory is /spl and the default <SPDIROUT> directory is /spl/sploutput.

When a user logs on to a particular environment of the product either using the browser-based interface or directly on UNIX/Windows, the environment is set up (i.e. environment variables, etc.) to point to the appropriate directory structure under the mount point. The environment variable that points to an environment directory under <SPDIR> is \$SPLEBASE (or %SPLEBASE% in Windows). The environment variable that points to an environment directory under <SPDIROUT> is \$SPLOUTPUT (or %SPLOUTPUT% on Windows). The SPLEBASE and SPLOUTPUT environment variables are two of the standard environment variables used by the utilities provided with the product and runtime.

Implementation Tip: The actual location of the application directory <SPLDIR> and application output directory <SPLDIROUT> is up to site standards. The product does not care where it is installed as it internally uses the environment variables to access the correct locations.

The actual location for the mount points can differ per environment if you want. This is handy if you need to vary the location because you do not have enough space for all your non-production environments. Typically the number of environments during an implementation varies according to the level of access and desired amount of testing and training. The only restriction is that there can only be one location for SPLEBASE and SPLOUTPUT per environment.

2.5 Software Directory Structure

The following components are stored in the base code directory structure:

- **Runtimes for Components** – All the runtime executables for the base software.
- **Business Object Binaries** – All the binaries that contain the business logic.
- **Configuration Files** – All the configuration files for the business objects and runtimes
- **Scripts** – Any administration or runtime scripts that are supplied to the customer.
- **Supported Plug-ins** – Source and executable for supplied plug-ins.

The following figure depicts the layout of where the product code is placed upon installation into the file system (where <environment> is the environment name chosen during the installation process):




Figure 5: Software Directory Structure

The following table outlines the typical contents of these directories:

Directory	Contents
bin	Utilities and commands for operations and configuration.
etc	A set of directories holding configuration files used in the product as well as template files and base libraries used to generate the configuration files.
java	Location of temporary files for java execution.
ks	Location of Key Stores
oem	Application Management Suite for Oracle Utilities ³ generated files
logs	Location of product specific log files
osbapp	Oracle Service Bus integration (optional)
product	Directories containing any bundled software with the product.
scripts	Directory containing any implementation specific scripts.
soaapp	Oracle SOA integration (optional)
splapp	Directories containing the J2EE Web Applications (see SPLApp).
structures	Internal structures used for configuration utilities.
templates	Base templates used to build configuration files.
tmp	Directory used to hold intermediary files used for the deployment process.
tools	Location of service pack, single fix and group fix utilities. See Tools.
updates ⁴	Location of installed_fixes.txt.

³ Files in this directory are generated by the discovery process used with the Oracle Application Management Pack for Oracle Utilities.

⁴ The `updates` directory only exists after at least one patch has been installed. If the directory does not exist then no patches have been installed on this environment.

2.5.1 Software (splapp) Directory

Under the `splapp` subdirectory for each environment there are a number of subdirectories:




Figure 6: Software (splapp) Directory

Directory	Contents
applications	Location of the Web application product files.
billView	Location of the online bill viewing files (Products supporting bill view only).
businessapp	Location of the business application product files.
certs	Location of security certificates
config	Location of temporary configuration files.
iws	Location of Native Web Services.
ohelpsource	Oracle Help engine source location
pending	Internal use only
security	Default location of domain security initialization files (Embedded Oracle WebLogic installations only).
servers	Default location of copies of configuration and associated files (Embedded Oracle WebLogic installations only).
standalone	Location of common Java libraries and the batch component of the product.
xai	Location of the Web services adapter configuration and Incoming service schemas.
xmlMetaInfo	Location of the service definitions for the product.

Warning: Under no circumstances should files be manually altered in these directories unless instructed by Oracle Support. The Oracle Utilities SDK will deposit files in the relevant locations in this structure using the Packaging component of the SDK or using the Development tools directly.

2.5.2 Tools Directory

Note: In past releases the utilities to install patches were included in each patch. This is not the case anymore as they are centralized as part of the installation.

These utilities are not usually executed manually but are part of general installations and automation from Application Management Pack for Oracle Utilities.

The tools directory is used for deployment and patching tools used by Application Management Pack for Oracle Utilities and the internal patching utilities. The directories are in the following structure:




Figure 7: Tools Directory Structure

Directory	Contents
bin	General Software patching utilities
bin/db	Database Patching utilities
bin/db/bin	Binaries for patching
bin/db/config	Logging configuration for patching utilities
bin/db/lib	Java Libraries for patching utilities
domaintemplates	Oracle WebLogic Domain Templates for product

2.5.3 Directory Permissions

Note: This facility on applies to Linux and UNIX platforms only.

The directories within the product are controlled by the operating system security relating to the administration user assigned to the product. The table below outlines the permissions under the \$SPLEBASE location:

Directory/Files	Owner	Group	Other
etc	rw	r	
Individual files	rw	r	
logs	rw	r	
logs/system	rw	rw	
Oracle WebLogic Configuration Files	rwx	rw	
Oracle WebLogic shell scripts (.sh)	rwx	rx	
product	rwx	rx	
product/apache-ant/bin/ant	rwx	rx	rx
runtime	rwx	r	
scripts, tools, updates	rwx	rx	
Shell scripts (.sh) in bin	rwx	rx	
osbapp, soaapp, splapp	rwx	rx	
structures	rwx	rx	
templates	rwx	rx	
tmp	rwx	rx	

Legend: r = Read Only, rw = Read Write, rwx = Read Write Execute, rx – Read/Execute, blank = no permissions.

These permissions are set by the setpermissions.sh utility which is executed as outlined in the *Oracle Revenue Management and Billing Installation Guide*.

2.6 Output Structure

The product processes (batch and online) that produce output and logs place information in this directory structure. The environment directories are referenced by the environment variable `SPLOUTPUT`. By default, this directory is created as `/spl/splapp`, though this can be substituted for an alternative during the installation process. The figure below illustrates the typical directory structure for this location (where `<environment>` is the environment name chosen during the installation process):




Figure 8: Output Directory Structure

Directory	Contents
logs/system	Directory containing application logs files. This is independent of Web application server, Business Application Server and Database Server log files.
logs/backup	Default location of backup of logs if <code>SPLBCKLOGDIR</code> is set.

The implementation may add subdirectories as their site standards and implementation dictates.

2.7 Environment Variables

The product uses a number of environment variables to determine where information is stored and to be placed for its internal operations. Becoming familiar with these variables will assist you in finding information quickly and efficiently.

Note:

If a custom script is written to access or write information to the product functionality, it is highly recommended that the following variables be referenced in your scripts. This is to maximize the chance that your script will remain functional across upgrades.

The following table outlines some of the key environment variables:

Variable	Usage
ADF_HOME	Location of the Oracle ADF files
ANT_ADDITIONAL_OPT	Options for ant as per the configuration settings at installation time
ANT_HOME	Location of <i>ant</i> build utilities
ANT_OPTS	Options for <i>ant</i> for Oracle SDK
ANT_OPT_MAX	Maximum memory settings for ant as per the configuration settings at installation time
ANT_OPT_MIN	Minimum memory settings for ant as per the configuration settings at installation time
CMPDB	Database Type (ORACLE)
DBNAME	Database Name
ENVFILE	Location and name of environment configuration file
HIBERNATE_JAR_DIR	Location of Hibernate Java library
HOSTNAME	Name of host (fully qualified)
JAVA_HOME	Location of JDK
LANG	Language for COBOL (<i>COBOL based products only</i>)
LC_MESSAGES	Messages for COBOL (<i>COBOL based products only</i>)
LD_LIBRARY_PATH	Library Path
NLS_DATE_FORMAT	Oracle NLS Date Format
NLS_LANG	Oracle NLS Language string
NLS_SORT	Oracle NLS Sorting
ONLINEBILLINI	Location of document rendering software template building configuration files
ONLINEDOCINI	Location of document rendering software configuration files
OPSYSTYPE	Operating System Name
OPSYSTIME/OPSYSTIMEZONE	Operating System Version

Variable	Usage
ORACLE_CLIENT_HOME	Location of the Oracle Client software (used for location of perl). If full Oracle Database software is installed on the host this value will match ORACLE_HOME
ORACLE_HOME	Location of the DBMS software
OSTYPE	Operating System Type
PERL5LIB/PERLIB	Location of Perl Libraries
PERL_HOME	Location of Perl
SERVER_ROLES	Roles enable for this server
SERVER_ROLE_BATCH	Whether the batch server is included
SERVER_ROLE_INTEGRATION	Whether the integration server is included
SERVER_ROLE_ONLINE	Whether the online server is included
SPLADMIN	Administration User ID
SPLADMINGROUP	Administration group
SPLApp	Name of root Web application WAR file.
SPLAPP	See SPLOUTPUT
SPLBCKLOGDIR	Location of backups of online log files (must be set manually)
SPLEBASE	Location of software for environment
SPLEENVIRON	Name of environment
SPLOUTPUT	Location of output for environment
SPLRUN	Location of runtime for environment
SPLSDKROOT	Location of SDK (Development environment only)
SPLSYSTEMLOGS	Location of product specific logs
SPLVERSION	Version identifier of product (prefixed with V)
SPLVERSION_NUM	Version number of product
SPLWAS	Web application Server type
WEB_DEPLOY_EAR	Determines whether the installation is native or embedded (true)

Variable	Usage
WEB_ISEXPANDED	Whether Web application is expanded or not (not = WAR/EAR files)
WEB_SERVER_HOME	Location of Web Application Server software
WL_HOME	Location of Oracle WebLogic installation (WebLogic supported platforms only)
XAIApp	Name of the XAI Application WAR file

Note:

If a custom script is written to access or write information to the product functionality, it is highly recommended that the following variables be referenced in your scripts. This is to maximize the chance that your script will remain functional across upgrades.

HIBERNATE_JAR_DIR is used for the installation process only. After installation is complete the jar files located at the locations specified by these environment variables are copied to the correct locations for execution.

Additional variable may be created by various operating system and product utilities. The list above constitutes the non-temporary variables.

2.8 Common Application Logs

When the product is operating the infrastructure logs messages within its own logs. For example, the database will log database errors or messages to the database logs, the J2EE Web application server will log Web Application errors or messages to the J2EE Web application server logs and so on. The name and location of these logs is set by relevant vendors of those logs. Refer to the documentation provided with that software on where logs are stored and their logging conventions.

The product additionally writes a number of application specific logs to \$SPLSYSTEMLOGS (or %SPLSYSTEMLOGS% on Windows):

- `spl_web.log` - Web application server application messages.
- `spl_service.log` - Business Application Server messages. If the Business Application Server exists on the same J2EE Web Application Server instance (i.e. as per a local install) as the Web application server for an environment then this log does not exist and all messages are written to the `spl_web.log`.
- `spl_iws.log/spl_xai.log` - Web Services Adapter messages.
- Background processing logs are located in \$SPLOUTPUT (or %SPLOUTPUT% on Windows) for the following:
 - `threadpoolworker.<threadpool>.<datetime>.log` - The `threadpoolworker` log for `threadpool` `<threadpool>` started at `<datetime>`.
 - `<batch_cd>.<datetime>.THD<thread>.stderr/<batch_cd>.<date time>.THD<thread>.stdout` - The submitter log for thread `<thread>` of background process `<batch_cd>` started at `<datetime>`.

The format of all logs is as follows:

Field	Comments
<userid>	User ID of transaction (blank or "-" for system generated messages)
<pid>	Process identifier (optional)
<time>	Time of transaction in format HH:MM:SS,SSS
[<transaction>]	Transaction/Class identifier
<type>	Type of message
(<class>)	Java class generating message (see Javadocs in appViewer)
<message>	<message contents>

Sample log entries:

```
19:03:16,390 [main] INFO (support.context.CacheManager) Registering
cache 'MenuRepository'

-19:02:37,812 [main] INFO (support.context.ContextFactory) 461
services registered, time 11.742 ms

-19:03:29,140 [Remote JVM:2 Thread 1] WARN (cobol.mem.CobolModeHelper)
Unspecified or unrecognized COBMODE (null) - inspecting JVM properties
to determine bit mode ...

19:03:40,875 [Thread-24] ERROR (web.dynamicui.MetaDataHolder) Unable
to find UI xml file '/an/generated/toDoSummaryListGrid.xml' for
program 'ToDoSummaryListGrid'

DEMO - 259992-101-1 19:17:38,750 [http-6500-5] INFO
(support.context.CacheManager) Registering cache 'UiMapInfoCache'
```

2.8.1 Automated Backup of Log Files

Note:

This facility is only supported using the embedded mode of Oracle WebLogic. If native mode is used then Oracle WebLogic log management is used.

Additional log management maybe specified in the log4j configuration files for individual components.

Logs associated with background processes are not backed up using this technique.

When the product is started with the `spl` command and if the `SPLBCKLOGDIR` environment is set then the logs are backed up to the location specified in the `SPLBCKLOGDIR` environment variable. If this variable is not set then the logs are removed prior to the start of the product.

The logs are backed up with the following pattern:

`$SPLBCKLOGDIR/<datetime>.<SPLENVIRON>.<logfilename>` (Linux/UNIX)

or

`%SPLBCKLOGDIR%\<datetime>.<SPLENVIRON>.<logfilename>` (Windows)

Where,

- <datetimestamp> : The date and time of the backup in the format YYYYMMDD.HHMM
- <SPLENVIRON> : The environment name
- <logfilename> : The name of the original file that is backed up.

2.9 Batch Concepts BATCH

Note:

The DISTRIBUTED mode supported in previous versions of the product has been removed in this release. Customers using this mode should migrate to CLUSTERED mode using either a single server configuration (ss) or unicast configuration (wka) using bedit.

Logs associated with background

The batch component of the architecture has a number of key concepts to understand.

2.9.1 Batch Clustering Concepts

As mentioned in the previous section, Oracle Coherence is used internally to cluster the resources needed for the batch architecture. This is similar in concept to a cluster used by the J2EE Web Application Server for online and web services.

- A cluster is one or more hosts that can execute batch processes. A cluster is named to delineate it from other clusters in your network. Oracle Coherence Named Caches are used to implement the cluster.
- Members of a cluster are hosts, threadpools and submitters. Each member is tracked by the cluster for high availability. At least one member must be active for a cluster to operate.
- Intracluster communication between members of the cluster can be achieved using uni-cast (also known as Well Known Addresses) or multi-cast.
 - In uni-cast implementations, each host and associated port is defined in the cluster. Each cluster member has definitions of other members. This mode is a less dynamic configuration⁵ but optimizes host to host communications for large clusters⁶.
 - In multi-cast (default) implementations, a multi-cast address and port are defined across the cluster which members attach to when executing. This mode is dynamic but traffic across nodes can be excessive for large clusters.
- A threadpool is a Java Virtual Machine (JVM) that executes batch threads. It is a long running JVM that batch threads are submitted to. Threadpools are named to group resources across a cluster when using multiple instances of a threadpool.
- A threadpool has a configurable maximum capacity for running batch threads to prevent overloading of JVM's⁷. Running multiple instances of a threadpool (within or across hosts) can increase the limit and implement high availability.

⁵ As each member must have its own configuration. To add or remove members requires manual synchronization of configuration files.

⁶ Large clusters are a large number of hosts, large number of threadpools and/or large number of threads executing at the same time.

- Clusters can support dedicated cache threadpools. In a cluster, each member can potentially communicate to each other member. In a large network this can cause network overheads that can adversely affect performance. To minimize the impact of network traffic, it is possible to configure a cache threadpool that will act as a central co-ordinator in the cluster to optimize and channel intramember communication.
- Clusters can support administration threadpools. In a cluster, it is possible to check on the status, in real time using JMX, across the cluster by connecting to any node in the cluster. It is possible to setup an administration node that can act as a single point of contact across the cluster to monitor performance, in a similar vein as the administration server in the J2EE architecture. These administration threadpools can be used by command line utilities, jconsole, Oracle Enterprise Manager via Application Management Pack for Oracle Utilities and/or Coherence Management Pack.
- Submitters are instances of individual background processes or individual threads of background processes that are submitted to a named threadpool. The submitter waits for the thread or background process to complete or abort and reports the status of the thread or background process to the operating system. This latter facility is used by Batch Scheduling tools to determine the status of the background process.
- Submitter can be targeted to specific instances of a threadpool or submitted to the cluster of threadpools. Submitters can execute specific threads or all threads in a single execution.

2.9.2 Batch Controls

Note: The system is delivered with all necessary batch controls for the supplied base background processes.

Background processes within the product must be defined using meta data (as well as physical code) to execute the process in the architecture. Refer to the online help and user documentation for details of the attributes associated with a batch control.

2.9.3 Standard Parameters

To standardize all the background processes, the product uses a number of common standard parameters to uniformly provide functionality across all processes. The table below lists all the standard parameters:

Parameter	Usage
Batch code	Code is the unique identifier of the background process
Batch thread number	Thread number is only used for background processes that can be run in multiple parallel threads. It contains the relative thread number of the process. For example, if the billing process has been set up to run in 20 parallel threads, each of the 20 instances receives its relative thread number (1 through 20).

⁷ Threads in background processing are typically heavier in terms of resource usage than typical java threads hence lower thread limits.

Parameter	Usage
Batch thread count	Thread count is only used for background processes that can be run in multiple parallel threads. It contains the total number of parallel threads that have been scheduled. For example, if the billing process has been set up to run in 20 parallel threads, each of the 20 instances receives a thread count of 20.
Batch rerun number	Rerun number is only used for background processes that download information that belongs to given run number. It should only be supplied if you need to download an historical run (rather than the latest run).
Batch business date	Business date is only used for background processes that use the current date in their processing. For example, billing using the business date to determine which bill cycles should be downloaded. If this parameter is left blank, the system date is used.
Commit Interval	Override maximum records between commits. This parameter represents the number of transactions that are committed in each unit of work. This parameter is optional and overrides the background process's Standard Commit between records (each background process's Standard Commit between records is documented in the product documentation). You would reduce these values, for example, if you were submitting a batch process during the day and you wanted more frequent commits to release held resources. You might want to increase these values when a background process is executed at night (or weekends) and you have a lot of memory on your servers.
User ID	This is the user ID that is used to access objects. It must be defined to the security component of the product.
Password	This parameter is not applicable (it is provided for backward compatibility).
Language	This is the language code used to retrieve messages and format output from background processes.
Traces	<p>Trace program at start (Y/N), trace program exit (Y/N), trace SQL (Y/N) and trace output.</p> <ul style="list-style-type: none"> • If trace program start is set to Y, a message is displayed whenever a program is started. • If trace program at exit is set to Y, a message is displayed whenever a program is exited. • If trace SQL is set to Y, a message is displayed whenever an SQL statement is executed. • If trace out is set to Y, message are output from the program at execution points.
	<p>Note: This facility should only be used in development.</p>

2.9.4 Additional Key Parameters

In all batch controls there are two additional parameters that may not be specified in the batch control definition but are available for use within each job:

- MAX-ERRORS (maxErrors) - This is the error tolerance for the job. When the number of errored records in a thread for a job has been exceeded that thread is stopped with an appropriate error code. This setting is to prevent large amounts of errors to influence the state of the job.
- DIST-THD-POOL (threadpool) - This allows a particular pool to be specified for the execution of the job. This is primarily used with online submission.
- emailMode - Defines the status for which an email notification⁸ is sent when a job ends. This does not apply to individual threads but when all threads are complete. Valid values are:
 - ERROR - Send an email when at least one thread ends in error status.
 - SUCCESS - Send an email when all threads end successfully.
 - ALL (Default) - Always sends an email when all threads end regardless of status.
- overrideLowIdValue - Specifies a new low id to use in calculating the range for a thread. The product by default assumes that the Id is between 0's (e.g. 000000000) and 9's (e.g. 999999999), but this parameter will override the low value. The product calculates each thread's low and high id by slicing the job's range into chunks using the thread number and count. It is typically more appropriate for sequentially allocated Ids to evenly distribute work among threads. The parameter value can be an actual number or it can be set to auto. If the parameter is set to auto, then the value is set to the lowest current value on the associated database table. The table name is determined from the batch program's query iterator
- overrideHighIdValue - Specifies a new high id to use in calculating the range for a thread. The product, by default, assumes that the Id is between 0's (e.g. 000000000) and 9's (e.g. 999999999), but this parameter will override the high id. The product calculates each thread's low and high id by slicing the job's range into chunks using the thread number and count. It is typically more appropriate for sequentially allocated Ids to evenly distribute work among threads. The parameter value can be an actual number or it can be set to auto. If the parameter is set to auto, then the value is set to the highest current value on the associated database table. The table name is determined from the batch program's query iterator.
- idRangeOverrideClass - Provides for a custom class to do thread range calculation. The class name specified must implement interface com.splwg.base.api.batch.BatchIdRangeOverride. During batch execution, this override class will be instantiated and the setter methods called to initialize the Ids as required. The low and high getter methods will be called to retrieve the high and low ids to be used for the run
- numRecordsToFlush - Defines how frequently to flush the Hibernate cache to prevent high heap consumption and OutOfMemoryErrors. In SingleTransactionStrategy there are no commits throughout the run, so this parameter can be used to flush the Hibernate cache periodically. This parameter is only applicable to jobs that use SingleTransactionStrategy.

Note: The parameters **overrideLowIdValue** and **overrideHighIdValue** are only applicable to jobs that use **ThreadIterationStrategy**.

⁸ This is used for online submission when an email address is provided on the job submission and the email server is configured.

These parameters may be added to the Batch Control or properties files used for running the job.

2.9.5 Batch Run Tree

Within the product browser interface there is an ability to monitor the status and outcomes of individual processes. This can be useful for finding out what actually occurred if an error condition occurred. Refer to the online help for more information about this facility.

The Batch Run tree is available to any valid user and is a method to communicate the execution information to the relevant business representatives.

2.9.6 Timed Jobs

Note: Monitor processes are ideal for Timed Jobs.

By default, background processes start and finish when they have processed the records it has selected at the start of execution. In this case, to process more records it is necessary to run the batch process again.

In some business processes, it may be necessary to continually execute a job to process work that is ready at any time. For example, processing payments, meter reads, asset changes or tasks as they appear. This situation is handled as a Timed Job. This Batch Control type is configured with a Timer Interval (the desired runtime between executions in seconds) and a Timer Active flag (to enable and disable the job activity).

When the Timer Active flag is set to true, the product executes the job for the duration of the Timer Interval before executing another instance of the job. This allows the job to run continuously over time, whilst the Timer Active flag is set to true.

Each instance of the job will start and stop using the following rules:

- The job will only execute when the Timer Active Flag is set to true. To the next execution from starting this value should set to false.
- The job will execute using the parameters on the Batch Control including the dedicated parameters for Timed Jobs such as UserID, Batch Language and Email Address.
- Once the Timer Interval has been reached, the job will commit after the latest transaction is complete and update the Batch Control is complete or errored (as appropriate).
- The next instance of the process is repeated as above.

Note: Due to varying transaction workloads the time taken may exceed the Timer Interval. This situation can be tracked using Level of Service if desired.

2.9.7 Level of Service

Note: For backward compatibility purposes, Level of Service is in the disabled state and requires configuration of targets in the Level of Service algorithm.

One of the features of the background processing architecture is that all executions of a Batch Control are tracked internally. This is typically expressed in the Batch Run Tree for information purposes but can also be used to calculate an indicator of the level of service if desired using the Batch Control - Level Of Service algorithm. Algorithms of this type return one of three levels of service:

- **Disabled** - Batch level of service algorithm is not enabled for the batch control or no data is available for comparison.
- **Error** - Indicates that errors were detected. In this case a message is also returned to indicate the issue.
- **Normal** - Indicated when there were no errors or issues detected by the algorithm.

Note: It is possible to write custom Level Of Service algorithms to compare any appropriate business metric.

The algorithm compares the last execution time and throughput to return three levels of service:

- **Disabled** - Batch level of service algorithm is not enabled for the batch control or no data is available for comparison⁹.
- **Error** - Indicates that errors were detected in the last execution of a background process, or that the amount of time between successive executions of a background process exceeded a specified target period.
- **Normal** - Indicated when there were no errors detected in the last batch run and the last batch run completed within the maximum number of seconds between successful runs, compared with the current running server time or throughput.

Typically Level of Service is only appropriate for Timed Jobs only to assess whether the timer interval is set efficiently but can apply to any background process.

Note: It is possible to write custom Level Of Service algorithms to compare any appropriate business metric.

2.9.8 Explanation of Commit Interval

The Commit interval parameter is a tuneable parameter to affect the impact of the background processes on the other processes running and prevent internal database errors. In most cases using the defaults will satisfy your site requirements. It is also important to understand their impact to ascertain whether any change is required.

During processing of any background process a main object is used to drive the process. Each process tables one or more objects to process. For example, billing processes accounts, meter reading processes meter reads or meter events, asset Processing uses assets, workforce processing uses tasks etc. For other processes it is other objects that are considered the main object. This status of the object or status of related transaction data is used to determine when a transaction is complete.

For the Commit interval this concept is important as:

- When a certain number of main objects have been processed then a database commit is issued to the database. This number is the expressed in the Commit Interval. The larger the commit interval the larger the amount of work that the database has to keep track of between commit points.

⁹ This can occur for the initial execution only.

Note: The number of records in progress utilizes redo log space so the size of the redo logs in the database and commit interval must be compatible. The higher the commit interval the more redo log space is required.

- At any time in a process a commit for objects processed may be caused by the reaching the Commit Interval or the end of the job, whichever comes first.

2.9.9 Explanation of Thread Limit and Thread Number

Note: Optimization discussions for these parameters are covered in the Batch Best Practices (Doc ID: 836362.1) available from [My Oracle Support](#).

One of the features of the Oracle Utilities Application Framework is the ability to run background processes using multiple threads.

The threading concept in the product is simple. Each thread takes a predetermined slice of the data to work on. The last thread checks if all other threads are finished and updates the status of the batch control records. For example, if you have 10 threads, then each thread takes 1/10th of the work. As each thread is executing it processes its workload and then completes, the last thread executing is responsible for updating the overall process status to indicate completion.

Implementing threading means you have to execute a number of background processes with an ascending thread number up to the thread limit. For example, if you have a background process with 10 threads, you must run 10 background processes each with a unique thread number between 1 and 10 to complete the background process. Threads can be located on the same machine or different machines. For example, you can run threads 1 to 5 on one machine and threads 6 – 10 on another.

Note: If there is limited data skew in the data then the threads should finish around the same time. If there is some data skew then some threads may finish later than others.

To implement multi-threading when you submit a process:

- Specify a thread limit greater than 1 as a parameter.
- Execute a background process for every thread with a sequential thread number up to an including the thread limit. There are a couple of implementation guidelines with threading:
 - Make sure the number of threads is not excessive. You do not want to flood the CPU's.
 - You must submit a process per thread. In some submission methods this is done automatically and in some it is done manually.
 - Threading will increase throughout BUT it will cause higher than usual resource usage (CPU, Disk etc) as well as higher contention. Excessive threading can in fact cause performance degradation in online as well as background processing. Therefore the number of threads should not be excessive.

Almost all background processes within the product support multiple threads (typically the only background processes that are single streamed are extracts and data loads as they involve reading and writing files).

2.9.10 Explanation of Restart and Rerun

The product allows all background processes to be restarted or rerun as required. During the execution of the background process, restart information per thread is stored within framework, like a checkpoint. This checkpoint is performed at the last commit point as dictated by the Commit Interval and/or

Timeout value (Time out only applied to Oracle implementations only). When a commit is performed, the last commit point is recorded for the execution. If a thread of a background process fails, the database automatically rolls back to the last commit point. The thread can then be restarted from that point automatically or from the start of the data. To indicate the restart, the thread is executed with the same parameters as the original.

Additionally, processes are re-runnable. A background process is re-runnable when you can specify a specific run number to be re-run as required or specify a specific business date to reprocess. Using a rerun number or a previously used business date are all that is required to rerun a process.

Note: Not all background processes use Run number as a run indicator. Refer to the online documentation for which batch processes are re-runnable.

2.9.11 Submission Methods

There are a number of methods for submission supported by the product.

- **Online Submission** - This allows testing users to submit batch jobs from the online component. This facility is typically used for non-production environments.

Note: Oracle strongly recommends that online submission is not used for Production environments.

- **Command Line Submission** - A number of commands are available to start/stop threadpools and jobs from the command line or from a third party scheduler.

2.9.11.1 Online Submission

One of the most important useful testing/demonstration facilities of the product is the ability to submit batch processes from the online component of the product. An authorized user can submit any batch process using an online batch submission page.

The on-line batch submission page enables you to request a specific background process to be run. Refer to the online help for a discussion on how to use the online submission function. When submitting a background process on-line, you may override standard system parameters and you may be required to supply additional parameters for your specific background process. After submitting your background process, you may use this page to review the status of the submission.

Basically the following process is used to submit background processes using the online submission method:

- The process to be executed is registered online as to be submitted (or queued). This marks the process execution as Pending. When you request a batch process to be submitted from on-line, the execution of the desired background process will result in the creation of a batch run. Just as with background processes executed through your scheduler, you may use the Batch Run Tree page to view the status of the run, the status of each thread, the run-instances of each thread, and any messages that might have occurred during the run.

Note: Your online submission record is assigned a status value so that you may know whether your batch process has been submitted and whether or not it has ended; however, it will not contain any information about the results of the background process itself. You must navigate to the Batch Run Tree page to view this detail.

- A background process is scheduled using the submission daemon which will pickup any Pending background process executions and execute them. When you save a record on the batch process submission page, the batch process does not get submitted automatically. Rather, it saves a record in the batch process table. A special background process will periodically check this table for pending records and will execute the batch process. This background process will update the status of the batch process submission record so that a user can determine when their batch process is complete.

Note: At installation time, your system administrator will set up this special background process or configure the scheduler daemon to periodically check for pending records in the batch process submission table. Your administrator will define how often the system will look for pending records in this table.

It should be noted that this special background process only submits one pending batch process submission record at a time. It submits a batch process and waits for it to end before submitting the next pending batch process.

Note: If you request a batch process to be run multi-threaded, the special background process will submit the batch process as requested. It will wait for all threads to complete before marking the batch process submission record as ended.

During execution the status of the execution in the batch run tree is updated as well as the original submission screen. If you wish the system to inform you when the background process completes, you may supply your email address. The email you receive will contain details related to the batch process's output; similar to the batch process results you would see from the batch run tree.

Note: This assumes that during the installation process, your system administrator configured the system to enable email notification. Your administrator may also override the amount of detail included in the email notification.

To use this facility the following must be enabled:

- The online submission daemon and DEFAULT threadpoolworker is configured using the following parameters:
 - The BATCHENABLED setting must be set to true.
 - The BATCHDAEMON setting must be set to true.
 - The BATCHTHREADS setting must be greater than zero.

Note: The default setting for BATCHTHREADS is 5 threads. This setting should only be altered if large numbers of testers need to use the DEFAULT threadpoolworker at the same time.

- An external DEFAULT threadpool and daemon is started using the -d Y option on the threadpoolworker or starttpw.sh command. For example: threadpoolworker.sh -p DEFAULT=5 -d Y

2.9.11.2 Command Line Submission

At a site implementing the product, the batch processes to be executed to support the business as well as perform expected maintenance on the system needs to be scheduled, managed and executed from a central point. In most sites, this is done by using a third party batch process scheduler that controls the scheduling and execution of any batch processes across a site.

To support the use of such a scheduler with any Oracle Utilities Application Framework based product(s) a number of scripts and related configuration files have been provided to allow the scheduler to execute the process batch processes.

The scripts and configuration files allows for three fundamental facilities that can be used by external scheduling tools:

- The interface is command line based (it can also be invoked using a java based API see the product javadocs within AppViewer for a description of the interface) which most external scheduling tools support.
- The command based utilities return a standard return code to indicate the batch process has been successful or has been unsuccessful. Actions dependent on return code within the scheduler can then be configured.
- The logs within the utilities provided are in a common format that can be interrogated by the external scheduler to provide finer grained actions (especially for unsuccessful executions).

For additional advice about interfacing external schedulers with the product refer to the

Batch Best Practices (Doc ID: 836362.1) whitepaper on [My Oracle Support](#).

The following guidelines apply:

- Any command should execute splenviron prior to execution.
- Threadpoolworkers should be started prior to running any batch job threads using the threadpoolworker or starttpw.sh command in the scheduler.
- Batch Job threads should be submitted using the submitjob command.
- If threadpoolworkers need to be shutdown the jmxbatchclient -k command should be used.

3. Operations

There are a number of common operations that a site will perform on the product. This section outlines the steps involved in these common operations.

Note: This section only applies to the embedded mode installation of the product. Customers using native mode installations should start and stop servers via the Oracle WebLogic console, WLST or Oracle Enterprise Manager.

3.1 Command Line Utilities

The product includes several command scripts to aid with its configuration and operation. This section provides information about these utilities.

3.1.1 bedit - Batch Edit BATCH

Note:

The splenviron[.sh] utility must be executed before this utility can be used. See splenviron.sh for details.

This facility is only available if "Enable Batch Edit" is set to true in the installation.

To simplify the configuration of batch a new administration facility has been introduced. The bedit[.sh] is provided to guide the administrator through the cluster, threadpool and submitter configuration process using templates.

Command Usage:

Linux/UNIX:

```
bedit.sh [-h] [[-g] [-t arg] [-b arg|-e arg|-l arg|-c|-s|-w] [file]] | [-A]
```

Windows:

```
bedit [-h] [[-g] [-t arg] [-b arg|-e arg|-l arg|-c|-s|-w] [file]] | [-A]
```

Where:

Command Line Option	Description
-h	Show command usage
--h	Show extended help
-g	Generate configuration from the template and exit immediately. The configuration file name may be specified explicitly or implicitly as described under Mutually Exclusive Arguments below.
-t arg	Template to use. Examples: wka for Well-Known-Addresses; mc for Multicast; ss for Single Server. This is optional. The default is determined from be_prefs, be.properties or be.default.properties, in that order

Mutually Exclusive Arguments:

Command Line Option	Description
-b arg	Configure batch code specific properties files. Maintains job.<arg>.properties files.
-e arg	Configure general submitter mode properties files. Supports THIN and LOCAL execution mode. Maintains submitbatch.<arg>.properties files.
-l arg	Configure threadpool label specific properties files. Maintains threadpoolworker.<arg>.properties files.
-c	Configure the cluster configuration. Shortcut name for tangosol-coherence-override.xml
-s	Configure the base submitter configuration. Shortcut name for submitbatch.properties.
-w	Configure the base threadpoolworker configuration. Shortcut name for threadpoolworker.properties.
file	The properties file to edit. This must be a valid batch properties or Coherence XML configuration override file. May be used instead of the shortcut forms above and must be the last argument if specified.

Exclusive Argument:

Command Line Option	Description
-A	Generate ALL the base configuration files and exit. Combines -c, -w and -s option. Option -A must be the only option if specified.

Examples:

```
bedit threadpoolworker.properties
bedit -t wka -c
bedit -c -l cache
```

Note: For more information about bedit[.sh] refer to the Configuring Batch using bedit section of this guide.

3.1.2 buildJavadocsIndex[.sh] - Builds Appviewer Java Docs

Note:

The splenviron[.sh] utility must be executed before this utility can be used. See splenviron.sh for details.

This utility is only used for development environments where javadocs must be generated for other developers to use and appViewer is installed and deployed.

This utility only works on custom java classes where source is provided with the customization installation and after the customizations have been installed.

The build AppViewer javadocs utility, buildJavadocsIndex, creates the javadocs for any custom java code for use for development. The utility does the following:

- After the custom java code has been installed using the SDK utilities, the utility generates the javadoc using the associated JDK.
- The utility optionally adds the generated to the javadoc to the product javadoc already installed in appViewer.
- Optionally regenerates the SPLWeb EAR file to update the appViewer.
- If running in embedded mode, the server needs to be restarted to reflect the change. If running in native mode the EAR file deployment needs to be updated.

Command Usage:

Linux/UNIX:

```
buildJavadocsIndex.sh [-h] [-n]
```

Windows:

```
buildJavadocsIndex.cmd [-h] [-n]
```

Where:

Command Line Option	Description
blank (without any command line option)	Generate javadocs and update SPLWeb EAR file
-h	Show usage.
-n	Generate javadocs but skip EAR update.

3.1.3 configureEnv – Setup Environment Settings

Note:

The splenviro[n].sh utility must be executed before this utility can be used. See splenviro[n].sh for details.

This utility can be used by both embedded and native mode customers. In native mode, some settings need to be specific values to support the native mode. Refer to the Installation Guide for further instructions on the use for the different modes.

The configureEnv[.sh] utility is an interactive method for configuring an environment on the system stored in the etc/ENVIRON.INI. This configuration script sets up important parameters used by other scripts within the system. Normally this script is executed without parameters and the current environment (i.e., the environment that you are currently attached to) is configured.

Command Usage:

Linux/UNIX:

```
configureEnv.sh ([-a] | [-g]) [-i] [-h]
```

Windows:

```
configureEnv.cmd ([-a] | [-g]) ([-c] | [-i]) [-h]
```

Where:

Command Line Option	Description
blank (without any command line option)	Configure basic configuration options
-a	Configure advanced configuration options
-c	Calculate variables only via silent mode. This refreshes ENVIRON.INI from individual changes
-g	Configure all configuration options (basic and advanced).
-h	Show usage.
-i	Configure Installation options (used for initial installation)

Refer to ENVIRON.INI for more information on the output of this command.

Note: If an unauthorized user attempts to execute this command the following error message – "Can't open/configure.log for output" is output.

3.1.4 createDBStandalone[.sh] - Creates Database Patches

Note:

The [splenviron\[.sh\]](#) utility must be executed before this utility can be used. See `splenviron.sh` for details.

This utility is used for patching only. Refer to the patch documentation for more information.

The `createDBStandalone[.sh]` utility, assembles all the needed components to allow database patches to be applied from a remote server. This utility creates the jar file named `db_patch_standalone.jar` containing the following:

- Relevant files in the bin directory needed for the patch.
- Relevant libraries needed for the patch.
- Relevant configuration files needed for the patch.

Command Usage:

Linux/UNIX:

```
createDBStandalone.sh [-h] [-l <location>]
```

Windows:

```
createDBStandalone.cmd [-h] [-l <location>]
```

Where:

Command Line Option	Description
blank	Performs complete extraction in default location SPLEBASE/tools/dbstandalone.
-h	Show usage.

Command Line Option	Description
-l <location>	Outputs jar file to the location <location>. If you do not specify a location then it will default to the blank action.

3.1.5 extractCMSourceUNIX[.sh] - Migrate Code Across Upgrades

Note:

The splenviorn[.sh] utility must be executed before this utility can be used. See splenviorn.sh for details.

This utility is only used for extracting development source from one environment to another. This is used for initial migration from Oracle Utilities Application Framework V2.x to Oracle Utilities Application Framework V4.x

This utility only works on custom java classes where source is provided with the customization installation and after the customizations have been installed.

This utility is only provided on Linux/UNIX platforms.

When migrating from Oracle Utilities Application Framework Version 2.x to Oracle Utilities Application Framework Version 4.x, this utility extracts the source that was retained in the upgrade and reorganizes it to conform to the newer structures used in Oracle Utilities Application Framework Version 4.x. This is used as an initial load only and does not need to be executed again once the reorganization is complete.

The utility does the following:

- Existing code customizations are extracted to a central location.
- The code customization are reorganized into the Oracle Utilities Application Framework Version 4.x format.

The applyCM utility provided with the Oracle Utilities SDK can then be used to install the customizations on an initial environment as outlined in the Software Configuration Management Series (Doc ID: 560401.1) available from [My Oracle Support](#).

Command Usage:

Linux/UNIX:

extractCMSourceUNIX.sh -v version -t target [-e] [-l lang] [-h]

Where:

Command Line Option	Description
-h	Show usage.
-v version	Version identifier for custom build. This is the build number that is used for CMVERSION.TXT. This parameter is required.
-t target	Directory location for files to be housed. applyCM will be run against this location in future steps. This parameter is required.
-e	Include any custom AppViewer and/or Help content. This parameter is optional.

Command Line Option	Description
-l lang	Specific language code to extract for Help content. If blank, all languages are extracted. This parameter is optional.

3.1.6 genappvieweritems – Generate AppViewer

Note:

The splenviron[.sh] utility must be executed before this utility can be used. See splenviron.sh for details.

This utility should only be executed if AppViewer is used in your environment (if the value of Deploy Application Viewer Module is set to true).

If the environment is used for reference or development then it may be necessary to regenerate the appViewer component from the metadata. A utility is provided that runs a number of provided background processes to regenerate the appViewer from the current environment.

Command Usage:

Linux/UNIX:

```
genappvieweritems.sh [-j] <job> [-Dshv]
```

Windows:

```
genappvieweritems.cmd [-j] <job> [-Dshv]
```

Where:

Command Line Option	Description
-h	Show usage.
blank (without any command line option)	Execute all extract jobs
-v	Display Version
-j <job>	Execute specific <job> from the following list: <ul style="list-style-type: none"> • F1-AVALG - Generate XML file(s) for Algorithm data • F1-AVMO - Generate XML file(s) for Maintenance Object data • F1-AVTBL - Generate XML file(s) for Table data • F1-AVTD - Generate XML file(s) for To Do Types XML • F1-AVBT - Generate XML file(s) for Batch Control Types XML
-S	Silent Mode (logs only)
-D	Debug Mode enabled (development use only).

Samples:

```
$ genappvieweritems.sh
```

...

Application Viewer is delivered with the system including cobol source code and xml services. This script will extend Application Viewer capabilities on site by generating additional items.

The Following Programs will be ran

```
F1-AVALG Generate XML file(s) for Algorithm data
```

```
F1-AVMO Generate XML file(s) for Maintenance Object data
```

```
F1-AVTBL Generate XML file(s) for Table data
```

```
F1-AVTD Generate XML file(s) for To Do Types XML
```

```
F1-AVBT Generate XML file(s) for Batch Control Types XML
```

The Application EAR file will also be re-created if required. Proceed (Y/N)?

...

Calling F1-AVALG

```
program F1-AVALG got a 0 response code
```

Calling F1AVMO

```
program F1-AVMO got a 0 response code
```

Calling F1-AVTBL

```
program F1-AVTBL got a 0 response code
```

Calling F1AVTD

```
program F1-AVTD got a 0 response code
```

Calling F1-AVABT

```
program F1-AVABT got a 0 response code
```

If you received a non response code 0 above, you should consult the logfiles

Note: For platforms that use WAR/EAR files, the genappvieweritems utility will automatically rebuild the WAR/EAR files ready for deployment (deployment will need to be performed if WEB_ISAPPVIEWER is set to true).

This generates the HTML files to be included in the appViewer application. This will only generate the necessary files from the current environment. To deploy the appViewer, the relevant option of initialSetup command must be executed to deploy rebuild the WAR file and redeploy the application.

Note: If an unauthorized user attempts to execute this command the following error message – "ERROR: Could not create a backup of log file." is output.

3.1.7 initialSetup – Maintain Configuration Settings

Note:

The initialSetup[.sh] script replaces the gen*[.sh] script provided with previous releases of the Oracle Utilities Application Framework.

The splenviron[.sh] utility must be executed before this utility can be used. See splenviron.sh for details.

Warning:

This command will reset all configuration files to template settings. Any direct customization to configuration files will be lost. Backup configuration files prior to running this script. If changes are necessary for your site then use user exits or custom templates to retain settings across executions of initialSetup[.sh].

During the installation and configuration process a number of configuration files used by the components of the architecture are built to be used by the various components of the architecture. The utility takes the ENVIRON.INI settings and using a set of provided templates (located in the etc directory), builds the necessary configuration files for the product components.

This utility has three functions:

- Build/Rebuild the configuration files from templates.
- Build/Rebuild the WAR/EAR files used by the product.
- Deploy the WAR/EAR files to the J2EE Web Application Server (IBM WebSphere/ND only). For customers using native mode, manual redeployment is necessary.
- Build/Rebuild the keystore files.

This concept is shown in the diagram below:




Figure 9: initialSetup Command Structure

While this utility is used at installation time and configuration to reflect configuration settings in the product, it can also be used to reset the configuration files to the original settings as well as reflect changes to the ejb-jar.xml - Enterprise Java Server Beans Configuration

The Business Application Server and MDB functionality uses Enterprise Java Server beans to implement service calls. By default the behavior of these components is defined and controlled with the ejb-jar.xml configuration file.

This configuration file is generated by the initialSetup using the templates/ejb-jar.xml.template file.

Note:

This configuration file is typically NOT altered unless custom JMS or MDB resources are to be included in the servers within the product.

Typically, JMS resources are not included in the server. Refer to the Oracle WebLogic JMS Integration (Doc ID: 1308181.1) whitepaper for details of JMS or MDB advanced configuration.

ENVIRON.INI - Environment Configuration File. Command Usage:

Linux/UNIX:

```
initialSetup.sh [-h] [-t] [-w] [-d] [-b] [-y] [-v] [-k] [-f] [-s]
```

Windows:

```
initialSetup.cmd [-h] [-t] [-w] [-d] [-b] [-y] [-v] [-k] [-f] [-s]
```

Where:

Command Line Option	Description
blank (without any command line option)	Process Templates, Build WAR/EAR files and Deploy to J2EE Web Application Server in one process.
-h	Show usage.
-t	Process Templates only
-w	Build WAR/EAR files only
-d	Deploy WAR/EAR files only (IBM WebSphere/ND only)
-b	Deploy Business WAR/EAR files only (IBM WebSphere/ND only)
-y	Deploy Web Application WAR/EAR files only (IBM WebSphere/ND only)
-v	Display Version
-s	Import Key Store from external location (KS_IMPORT_KEYSTORE_FOLDER)
-k	Generate Key store
-f	Force Task, skipping any warnings (used for silent installs only)

Examples:

```
$ initialSetup.sh
100207.02:37:33 <info> Template generation step.
100207.02:37:43 <info> FW template generation step.
100207.02:37:43 <info> Create war file for SPLApp.war.
100207.02:38:14 <info> Create war file for XAIApp.war.
100207.02:38:26 <info> Create war file for appViewer.war.
100207.02:39:14 <info> Create war file for help.war.
100207.02:41:11 <info> FINISHED INITIAL INSTALL SETUP at Thu Aug 7
02:41:11 EST 2009
100207.02:41:11 <info> See file
/spl/TRAINING/logs/system/initialSetup.sh.log for details
```

Note: If an unauthorized user attempts to execute this command the following error message – "ERROR: Could not create a backup of log file." is output.

3.1.8 installSFGroup[.sh] - Install Software Patches

Note:

The splenviron[.sh] utility must be executed before this utility can be used. See splenviron.sh for details.

This utility is located in the tools/bin directory of the software installation.

This utility does not handle prerequisites unless used with the PatchDeployUtility.

This utility only does software installation. Database installation is handled by ouafDatabasePatch.

The installSFgroup utility installs a single or group of software fixes that have been downloaded.

Command Usage:

Linux/UNIX:

```
installSFgroup.sh -f InputFile -d InputDir -p product -v version -e
splenviron -r splebase -l logfile
```

Windows:

```
installSFgroup -f InputFile -d InputDir -p product -v version -e
splenviron -r splebase -l logfile
```

Where:

Command Line Option	Description
-f InputFile	Fill path of list of single fixes to install. This can be generated from PatchDeployUtility, included in a service pack, included in a fix or manually created.
-d InputDir	Location of single fixes downloaded from My Oracle Support . These must be unzipped.
-p product	Product Name for patch file (this is the prefix of the file) (optional)
-v version	Version number of files (optional)
-e splenviron	Environment Name to apply fixes to. Defaults to current SPLENVIRON environment variable if not specified.
-r splebase	Root location of software for environment. Must match value in /etc/cistab. Defaults to current SPLEBASE environment variable if not specified.
-l logfile	Name of log file to output. Defaults to install.log if not specified.

3.1.9 invokeDBUpdatePatch[.sh] - Regenerates passwords in Installation Options

Note:

The splenviron[.sh] utility must be executed before this utility can be used. See [splenviron.sh](#) for details

The invokeDBUpdatePatch[.sh] utility, updates the Installation options that use encryption for key updates.

It is recommended to refer to the [Keystore Configuration \(Doc ID 2014161.1\)](#) whitepaper for details of how and when to use this utility.

3.1.10 iwsdeploy - Inbound Web Services Deployment

Note: The splenviron[.sh] utility must be executed before this utility can be used. See [splenviron.sh](#) for details.

The Inbound Web Services deployment utility, iwsdeploy, creates the Web Services EAR file and also deploys that EAR file to the servers. The process does the following:

- Extracts the Inbound Web Services that are new or changed as indicated on the deployment record (status of Needs Repdeployment).
- For each Web Service generates a number of artefacts required by the Web Application Server to define and execute the Web Service.
- Builds the components into a EAR file called Webservices.ear located in the \$SPLEBASE/splapp/iws/gen directory (or %SPLEBASE%\splapp\iws\gen directory on Windows).
- Deploys the EAR file to the container configured.

It also is possible to perform this activity using the Inbound Web Services Deployment online function. It is recommended that in non-production both methods are available but in production iwsdeploy is used.

The iwsdeploy does not have any options at the present time.

Command Usage:

Linux/UNIX:

iwsdeploy.sh

Windows:

iwsdeploy.cmd

3.1.11 jmxbatchclient[.sh] – JMX Batch Command Line BATCH

Note:

The splenviron[.sh] utility must be executed before this utility can be used. See [splenviron.sh](#) for details.

For more examples of usage of this command refer to the Batch Best Practices (Doc ID: 836362.1) available from [My Oracle Support](#).

This facility will only operate if the BATCH_RMI_PORT is populated.

The batch architecture while the JMX client interface is provided allows real time information to be displayed in a JMX browser, if a JMX browser is not used then the JMX interface may be interfaced using a command line utility. This utility is useful to allow third party products (such as batch schedulers) or other systems to control and monitor the state of the system.

This JMX batch command line allows the following to be performed:

- Identify what thread pools are defined in a threadpoolworker
- See what active batch processes or threads are currently running
- Be able to cancel a particular thread or a batch process
- Gracefully shutdown a threadpoolworker

To execute the command line, the administrator must:

- Logon to the machine running the product (any tier where the product software exists).
- Attach to the environment using the `splenvirion[.sh]` command. This sets the appropriate environment settings for the script.
- Execute the JMX Batch command line utility:

```
jmxbatchclient[.sh] -j [URL] [options]
```

Where [options] are:

Command Line Option	Description
<code>-c</code>	Specifies that active threads should be cancelled. Can be used with <code>-f</code> option to cancel only batch processes matching the regular expression provided. For example:
	Note: Cancelled threads are marked with the date, time, userID and IP address of the user who initiated the cancel command.
<code>-d</code>	Display the details of the currently active threads.
<code>-f</code>	If a large number of threads are currently active, a filter can be supplied to only display or cancel threads that match the regex based pattern. For example the threadpool be filtered to show only the BAT1 with the option: <code>-f</code> <pre>.*BAT1.* as follows: jmxbatchclient.sh -j service:jmx:rmi:///jndi/rmi://myserver:9999/oracle/ouaf/batchConnector -f .*BAT1.*</pre> Would yield: Options: -j <pre>service:jmx:rmi:///jndi/rmi://myserver:9999/oracle/ouaf/batchConnector -f .*BAT1.* Connecting to service:jmx:rmi:///jndi/rmi://myserver:9999/oracle/ouaf/batchConnectorActi veGridNode</pre> threadPools=[MYSERVER:5, LOCAL_THREAD_POOL:b9835d11f15fd71b:681ba91d:1200151a3c8:-8000:0, SCHEDULER_DAEMON_THREAD_POOL:1] BatchThread_ZZQABAT1_1_of_1.31
<code>-h</code>	Display the available options and their descriptions.

Command Line Option	Description
-j	JMX URL to perform the action against (Required). This should match the spl.runtime.management.connector.url.default property specified in the threadpoolworker.properties.
-k	Specifying this option will result in the cancellation of all currently running threads and the stoppage of the threadpoolworker process.
	Note: Active threads within a cancelled threadpoolworker are marked with the date, time, userID and IP address of the user who initiated the kill command
-l	By default, all logging information is displayed and logged using log4j. Supplying this option will result in only select information being displayed to the system output.
-s	Display the summary of the currently active threads in a listing format.
-t<wait>	Amount of time, in ms, to wait as expressed in <wait> for active jobs to cancel.
-z	Display the cache details. Must be used in conjunction with -j option.

3.1.12 ouafDatabasePatch[.sh] - Install Database Patches

Note:

The splenviron[.sh] utility must be executed before this utility can be used. See splenviron.sh for details.

For more information about patching refer to the Software Configuration Management Series (Doc ID: 560401.1) available from [My Oracle Support](#).

The ouafDatabasePatch allows database patches to be installed from the command line or via the Application Management Pack for Oracle Utilities. This utility is a companion to with installSFGROUP which installs the software component of patches.

Command Usage: Linux/UNIX:

```
ouafDatabasePatch.sh [-h] [-u] [-v] [-x] [-t toolsdir] [-p ouafparms]
```

Windows:

```
ouafDatabasePatch [-h] [-u] [-v] [-x] [-t toolsdir] [-p ouafparms]
```

Where:

Command Line Option	Description
-h	Show usage for patch.
-u	Show usage of command
-v	Display version of patch
-x	Database Password for applying patch

Command Line Option	Description
-b	Location of tools bin directory
-p	Additional parameters passed to utility (as per patch documentation). This must be the last parameter on the command line. This is primarily used by the Application Management Pack for Oracle Utilities.

3.1.13 PatchDeployUtility[.sh] - Create and Deploy Patch Rollups

Note:

The splenviron[.sh] utility must be executed before this utility can be used. See splenviron.sh for details.

For more information about patching refer to the Software Configuration Management Series (Doc ID: 560401.1) available from [My Oracle Support](#).

The PatchDeployUtility allows prerequisite product software and database patches to be analyzed, downloaded and applied in a single installation. This utility can be used from the command line or via the Application Management Pack for Oracle Utilities.

There are three phases for the utility to execute:

- Report Mode - Generate a patch dependency list for a particular patch.
- Download Mode - Download the patches not already downloaded from the Report mode list.
- Rollup Mode - Create a single installer to install all the patches in the patch dependency list in one install.

Note: This utility does not install the patches. They must be installed using the installSFgroup and ouafDatabasePatch utilities.

Command Usage: Linux/UNIX:

```
PatchDeployUtility.sh -f patchfile -m mode -l missingfile -d dir -r dir -n missingfile
```

Windows:

```
PatchDeployUtility.sh -f patchfile -m mode -l missingfile -d dir -r dir -n missingfile
```

Where:

Command Line Option	Description
-f patchfile	The full path and file name to the patchdependency.txt file of the patch to use as a reference point. This parameter is used by the REPORT mode only and is required for that mode.
-m mode	Mode. Supported values: REPORT, DOWNLOAD or ROLLUP.
-l missingfile	Full path and file name for output for REPORT mode. This file will contain the list of fixes that have not been downloaded. This parameter is used by the REPORT mode only and is required for that mode.

Command Line Option	Description
-d dir	Full path to location where any missing patches will be downloaded to when using the DOWNLOAD mode. This is also used by the ROLLUP mode as a source directory.
-r dir	Fill to location where the rollup files will be generated. This is the location used by the installSFGroup and ouafDatabasePatch utilities will be executed from. This parameter is by the ROLLUP mode only and is required for that mode.
-n missingfile	Full patch and file name of the missing patches generated by the REPORT mode. This parameter is used by DOWNLOAD and ROLLUP modes.

For example:

```
PatchDeployUtility.sh -f
/scratch/mypatches/fix10001/patchdependency.txt -m REPORT -l
/scratch/patches/missing.txt
PatchDeployUtility.sh -n /scratch/patches/missing.txt -m DOWNLOAD -d
/scratch/mypatches
PatchDeployUtility.sh -n /scratch/patches/missing.txt -m ROLLUP -d
/scratch/mypatches -r /scratch/myrollups
```

3.1.14 showjavaproc[.sh] - Show Java Processes

Note:

The splenviron[.sh] utility must be executed before this utility can be used. See splenviron.sh for details.

This utility is only provided on Linux/UNIX platforms.

This utility is mainly useful for embedded installations. It can be used for native installations but the environment name will not be rendered.

The showjavaproc utility lists the process ids for the WebLogic servers installed on the machine.

Command Usage:

Linux/UNIX:

```
showjavaproc.sh [-e envname] [-q]
```

Where:

Command Line Option	Description
blank (without any command line option)	Find all of the WebLogic servers running on the machine
-e envname	Filter the output by environment name. If it is found then output a 1 return code

Command Line Option	Description
-q	Do not put output on screen. Useful for custom scripting.

For example:

```
showjavaproc.sh -e MYENVIRON || echo "Weblogic Java Process is running"
```

```
showjavaproc.sh -e MYENVIRON && echo "Weblogic Java Process is NOT running"
```

3.1.15 splenviron – Set Environment Variables

Note: On the Linux/UNIX environment this utility creates a subshell upon completion.

The splenviron[.sh] utility initializes a defined set of environment variables and paths for an environment. This script must be run before any other script or utility is run within the environment.

Command Usage:

Linux/UNIX:

```
splenviron.sh -e <environment> [-c <command>] [-q] [-h]
```

Windows:

```
splenviron.cmd -e <environment> [-c <command>] [-q] [-h]
```

Where:

Command Line Option	Description
-e <environment>	<environment> is the environment id as installed in the cistab file.
-c <command>	Execute <command> after running splenviron[.sh]. Command must be enclosed in double quotes (""). Default is shell (e.g. ksh).
-q	Quiet Mode. Do not show output from command. Any output from the -c command will be shown.
-h	Show usage.

Samples:

```
splenviron.sh -e DEMO
```

```
splenviron -e DEV
```

```
splenviron.sh -e DEMO -c "cat file.lst"
```

The splenviron[.sh] utility is executed whenever an environment needs to be initialized. One of the options to this script allows system administrators to optionally include the execution of an additional command as part of the environment initialization. This enables the system administrator to more finely tune the environment shell so they can change such settings as TimeZone, PATH or environment variables.

3.1.15.1 Extending the splenviron Command

If your implementation needs to add environment variables (or modify existing variables) for a third party product you may wish to integrate with that product. For example, you might want to add some custom Java classes from a component that you want to use with the product.

When you run the `splenviron[.sh]` utility it sets the environment variables for the environment. These are standard variables as well as any required for operation of the product. For example, there are variables that can be used in utilities so they can be used across environments.

These environment variables can be extended (or added to) using one of the following options:

- Change to ALL environments on machine - If your integration is common across all environments then you can set or alter environment variables using the following technique:
 - Create a script in a central location on the machine that sets or alters the appropriate environment variables. Ensure that the product administrator User ID has read/execute access to the location and the script.
 - Set the `CMENV` environment variable with the location and name of the script to execute prior to running the `splenviron[.sh]` utility (for example, in your logon profile).
 - When the `splenviron[.sh]` utility is run it will detect the script specified in the `CMENV` environment variable and execute the script to set or alter the environment variables.
- Change to a specific environment on machine - If your integration is specific to an environment (or different for each environment, for example if you have a development as well as a test copy of the third party product) then you can set or alter environment variables using the following technique:
 - Create a script called `cmenv.sh` (or `cmenv.cmd` on Windows) in scripts subdirectory of the environment (usually `$SPLEBASE/scripts` or `%SPLEBASE%\scripts`). Ensure the permissions are set appropriately for the product administration account to execute the script.
 - When the `splenviron[.sh]` utility is run it will detect the `cmenv.sh` script (or `cmenv.cmd` on Windows) and execute the script to set or alter the environment variables at the end of the `splenviron[.sh]` utility.
- Combination of both previously outlined options – It is possible to combine the techniques in a combination which can mean you can have maximum flexibility. If you follow the instruction of both techniques then the following will happen in the following order:
 - When the `splenviron[.sh]` utility is run it will detect the script specified in the `CMENV` environment variable and execute the script to set or alter the environment variables.
 - If there is a `cmenv.sh` script (or `cmenv.cmd` on Windows) in the scripts subdirectory of the environment, it will execute the script to set or alter the environment variables. This may override, add or alter environment variables already set.

In using this override technique, remember:

- If you alter any pre-existing environment variables then ensure your changes are not going to circumvent product requirements. For example, do not alter paths used by the product.
- If you add files or directories to library variables or `CLASSPATH` ensure your changes are suffixed at the end of the variable. This is especially important for java classes as classes you use may

conflict with product supplied ones; adding them at the end of the CLASSPATH will minimize the effects of conflicts.

- Do not remove any environment variables used by the product.

3.1.16 spl – Start/Stop Environment

Note:

The splenviro[n].sh utility must be executed before this utility can be used. See splenviro[n].sh for details.

This utility should not be used for native mode customers. Use the console or scripts supplied with Oracle WebLogic to start or stop the product. Refer to the Oracle WebLogic documentation for information on this capability.

The spl[.sh] utility is used to start up and shut down an environment or individual components (web server or multi-purpose listener) of an environment. Usage of this utility is optional in sections of this document.

Use the command without a parameter to start up, reboot or shut down all components of an environment (note that the action must still be used). To start up or shut down an individual component, use the option that specifies that applies to that specific component.

Command Usage:

Linux/UNIX:

spl.sh [-h] [-wsba] [-q] <action>

Windows:

spl.cmd [-h] [-wsba] [-q] <action>

Where:

Command Line Option	Description
-h	Show usage.
blank (without any command line option)	Perform <action> on Web application server/Business Application only
-w	Perform <action> on Web application server only
-s	Perform <action> on Business application server only
-b	Perform <action> on batch component only. DEFAULT threadpool only. BATCH
-a	Perform <action> on all components
-q	Quiet Mode – Non-critical output goes to log file only

Command Line Option	Description
<action>	start – start the component/environment stop – stop the component/environment check – Check the status of the environment

When executed the script returns the following return codes:

Return Code (\$?)	Comments
0	Command executed successfully
1	Command executed unsuccessfully

Note: The command may issue other commands that need to be tracked separately depending on the platform. For Example

Action	Linux/UNIX Command	Windows Command
Start Application Server	spl.sh start	spl start
Stop Application Server	spl.sh stop	spl stop
Start all components	spl.sh -a start	spl -a start
Stop DEFAULT threadpool	spl.sh -b stop	spl -b stop
Start Business Application Server	spl.sh -s start	spl -s start
Stop Web Application Server	spl.sh -w start	spl -w start

3.1.17 starttpw[.sh] - Start Threadpoolworker

Note:

The splenviron[.sh] utility must be executed before this utility can be used. See splenviron.sh for details.

This utility is only provided on Linux/UNIX platforms.

This utility is useful for developers.

This utility is a wrapper utility that calls the threadpoolworker script for use in command line batch submitters or from the command line.

Command Usage:

Linux/UNIX:

starttpw.sh [-h] [-Q] [threadpoolworker options]

Where:

Command Line Option	Description
blank (without any command line option)	Execute the [threadpoolworker options] in the background (nohup).
-h	Show usage.
-Q	Execute the [threadpoolworker options] in the foreground

3.1.18 submitjob[.sh] - Submit Batch Threads BATCH

Note:

The splenviron[.sh] utility must be executed before this utility can be used. See splenviron.sh for details.

For more examples of usage of this command refer to the Batch Best Practices (Doc ID: 836362.1) available from [My Oracle Support](#).

The following options can be specified when executing utility submitjob[.sh]:

```
submitjob[.sh] [-B] [-b] [-c] [-d] [-e] [-f] [-g] [-h] [-i] [-J] [-l] [-L] [-m] [-n] [-p] [-P] [-Q] [-R] [-r] [-s] [-t] [-u] [-x] [-X]
```

where command line options are:

Command Line Option	Description
-b <batch code>	Batch code of the batch process to submit. When submitting a batch process, a batch code is always required. Either this option or -P may be specified, not both. If this option is specified, submitjob will use the supplied batch code to look for a default properties file for that batch code (e.g. VAL- SA.properties or VAL- SA.properties.xml as discussed above) and use those properties if found.
-c <thread count>	Concurrent number of threads in which to run the process.
-d <date>	Process / business date. Format is YYYY-MM-DD
-e <THIN CLUSTERED>	Execution mode for this submission. If execution mode THIN is selected, the JVM will create a full application context and run the batch process inside the JVM – i.e. it will not be submitted to a thread pool for a worker JVM to pick up and run. This is analogous to running the batch process using the existing SPLBATCH[.sh] utility. THIN mode is for development purposes only. If CLUSTERED is selected, the batch process will be submitted to run in the specified distributed thread pool (option -p). It is also possible to have the submitter JVM be a worker JVM and run the batch process (similar to THIN mode, but in parallel threads). See option -L.

Command Line Option	Description
-f <record count>	Record commit frequency count.
-g <four Y N switches>	<p>Positional tracing switches:</p> <ol style="list-style-type: none"> 1. Program entry 2. Program exit 3. SQL statements 4. General program debugging info <p>For example, NNYN will trace all SQL statements. Value of NNNN disables all tracing.</p>
-h	Show help information. Display the available options and their descriptions. The information is not logged.
-i <RMI port number>	Port number of RMI Registry to start and/or reference. If specified with -R, this number will be used only to substitute applicable URL {port} references. This option will not add any new RMI/JMX properties - it can only be used to override existing ones. See note below
-J	<p>Do not start JMX connector. This option disables JMX monitoring for this JVM. As far as submitjob is concerned, options -i, -R and -J are only applicable to batch processes submitted in THIN mode, or DISTRIBUTED or CLUSTERED mode to the LOCAL thread pool.</p> <p>For each property prefixed by <code>spl.runtime.management.connector.url</code> that is defined with the default set of properties (e.g. in the <code>submitbatch.properties</code> file), the framework will start a JMX Connector for the specified URL.</p> <p>This activates JMX monitoring inside the worker node so that a client JMX console can be used to monitor and manage active threads. If this option is specified, the framework will not start any JMX connectors.</p>
-l <ENG FRA etc.>	Language code. Relevant language pack must be installed.
-L	<p>Submit this batch to the LOCAL thread pool (i.e. this JVM). Only applicable for DISTRIBUTED or CLUSTERED mode. If specified, any default thread pool property is ignored. This option and -p are mutually exclusive.</p> <p>By specifying option -L, the batch process is submitted to the LOCAL thread pool that every submitter JVM offers by default. This option is only applicable in a DISTRIBUTED or CLUSTERED mode execution (-e). This is similar to submitting the batch process in THIN mode (i.e. a worker JVM is not needed to run the batch process), except thread pool LOCAL can run multiple batch threads concurrently.</p> <p>For example, the following command will run batch process <code>VAL-SA</code> inside this submitter JVM (LOCAL thread pool) in 8</p>

Command Line Option	Description
	<code>threads concurrently: submitjob[.sh] -b VAL-SA -c 8 -L -e DISTRIBUTED</code>
<code>-n <email address></code>	Send a notification email when a batch process has ended to <code><email address></code> . See Sending emails at the conclusion of batch processs for more information.
<code>-p <threadpool name></code>	Distributed thread pool in which to run the batch process. This option and <code>-L</code> are mutually exclusive.
<code>-P</code>	Issue console prompts for the standard batch process parameters. When submitting a batch process, a batch code is always required. Either this option or <code>-b</code> may be specified, not both. If <code>-P</code> is specified, the submitter JVM will prompt for the batch code and other run parameters. If a batch-specific properties file exists for the batch code entered at the prompt, it will NOT be used; the only defaults in effect would be the ones specified in <code>submitbatch.properties</code> .
<code>-Q</code>	Preview the properties that would be in use for the run without actually running the application. Specify other options along with this option to show how they would override or substitute the default properties. The information is not logged.
<code>-R</code>	<p>Do not start a local RMI registry. As far as <code>submitjob</code> is concerned, options <code>-i</code>, <code>-R</code> and <code>-J</code> are only applicable to batch processes submitted in <code>THIN</code> mode, or <code>DISTRIBUTED</code> or <code>CLUSTERED</code> mode to the <code>LOCAL</code> thread pool. If property <code>spl.runtime.management.rmi.port</code> is defined as a default property (e.g. in the <code>submitbatch.properties</code> file), the batch framework will attempt to start an RMI registry on the given port number.</p> <p>This option can be used to suppress the automatic RMI registry startup. It may be required if an externally started RMI registry is already running. Note that if this option is used, the RMI port number supplied through the <code>-i</code> option is only used for substitution in the JMX Connector URLs.</p>
<code>-r <run number></code>	Run number of batch process to rerun.
<code>-s <space name></code>	Space name for hard partition of workers. Default is <code>MAIN</code> . Used for development only.
<code>-t <thread number></code>	Number of individual thread for this submission. Specify 0 to automatically submit all threads.
<code>-u <user id></code>	Application User ID used for batch process
<code>-x <name=value, name=value, ...></code>	Name=value pairs of INDIVIDUAL soft parameters expected by the batch program. Value portion may be enclosed in quotes. These parameters will be merged with any existing (defaulted)

Command Line Option	Description
	soft parameters. This option and -X are mutually exclusive.
<code>-X <name=value, name=value, ...></code>	Name=value pairs of ALL soft parameters expected by the batch program. Value portion may be enclosed in quotes. These parameters will replace all existing (defaulted) soft parameters. This option and -x are mutually exclusive.
<code>-z <jvmoptions></code>	Java options to use for submitter.

This utility returns two return codes:

- Zero (0) - The job or thread was successful.
- Non-Zero - The job or thread was NOT successful.

3.1.19 `threadpoolworker[.sh]` - Manage Threadpools BATCH

Note:

The `splenviron[.sh]` utility must be executed before this utility can be used. See `splenviron.sh` for details.

For more examples of usage of this command refer to the Batch Best Practices (Doc ID: 836362.1) available from [My Oracle Support](#).

The following options can be specified when executing script `threadpoolworker`.

`threadpoolworker[.sh] [-d] [-e] [-h] [-i] [-J] [-p] [-Q] [-R] [-s]`

Where command line options are:

Command Line Options	Description
<code>-d <Y N></code>	Whether the node is acting as a scheduler daemon. Specify N for No and Y for Yes. If you are already using a scheduler daemon in the online system or are not using online submission then set this to N. Default is N.
<code>-e <THIN CLUSTERED></code>	Execution mode for this threadpool. If CLUSTERED is the threadpool will join the cluster specified in the <code>threadpoolworker.properties</code> file.
<code>-h</code>	Show command line help. List the available options and their descriptions. It is formatted for a 121- column width display. The information is not logged.
<code>-i <RMI Port></code>	Override port number for JMX. If specified with -R, this number will be used only to substitute applicable URL {port} references. This option will not add any new RMI/JMX properties - it can only be used to override existing ones. This option specifies the port number to: <ul style="list-style-type: none"> • Use when the framework starts an RMI Registry and • Substitute in all JMX Connector URL {port} references.

Command Line Options	Description
-J	Do not start JMX monitoring. For each property prefixed by <code>spl.runtime.management.connector.url</code> that is defined with the default set of properties (e.g. in the <code>threadpoolworker.properties</code> file), the framework will start a JMX Connector for the specified URL. This activates JMX monitoring inside the worker node so that a client JMX console can be used to monitor and manage active threads. If this option is specified, the framework will not start any JMX connectors.
-12<READ_ONLY READ_WRITE OFF>	Enable or disable batch caching. Default: <code>READ_WRITE</code> . <code>OFF</code> and <code>READ_ONLY</code> are reserved for specific processes
-p <name=value, name=value, ...>	Thread pool(s) offered by this worker node. Consists of one or more <code>name=value</code> pairs, where "name" is the name of the pool and "value" the number of threads offered in the pool. For example, <code>DEFAULT=5,ONLINE=3</code>
-Q	Preview the properties that would be active for this run. Used for testing. Preview the properties that would be in use for the run without actually running the application. Specify other options along with this option to show how they would merge with, override or substitute the default properties. The information is not logged.
-R	Do not start a local RMI registry. If property <code>spl.runtime.management.rmi.port</code> is defined as a default property (e.g. in the <code>threadpoolworker.properties</code> file), the batch framework will attempt to start an RMI registry on the given port number. This option can be used to suppress the automatic RMI registry startup. It may be required if an externally started RMI registry is already running.
	Note: If this option is used, the RMI port number supplied through the <code>-i</code> option is only used for substitution in the JMX Connector URLs.
-s <space name>	Space name for "hard partition" of workers. Default is <code>MAIN</code> . Reserved for internal use only.
-sf <file-path>	Generate or append command to a script. Reserved for system use.
-s1 <line to add to script>	Add line to script reference. Reserved for system use.
-z <jvm options>	Add or override JVM options for threadpool.

When `threadpoolworker` is invoked, the command-line options will alter its default configuration. The default configuration options come from either internal system defaults or the `threadpoolworker.properties` file described above.

The properties are overridden in the following order:

1. The `threadpoolworker.properties` supersedes the internal system defaults.

2. The command-line options supersede the defaults in `threadpoolworker.properties` and the internal system defaults.

Example 1

Assuming we have the above set of properties in `threadpoolworker.properties` and script `threadpoolworker` is invoked as follows:

```
threadpoolworker[.sh] -d Y
```

This will replace the default "daemon" property to "N" (i.e. false) so that the properties now look as follows:

```
com.splwg.grid.distThreadPool.threads.DEFAULT=5
com.splwg.grid.distThreadPool.threads.LOCAL=0
com.splwg.batch.scheduler.daemon=false
spl.runtime.management.rmi.port=9999
spl.runtime.management.connector.url.default=service:jmx:rmi:///jndi/rmi://:{host}:{port}/oracle/ouaf/batchConnector
```

3.2 Attaching to an Environment

Note: This command is not necessary if using the Oracle WebLogic native support when managing the product from the Oracle WebLogic console.

Before performing any command against a product environment, you must attach to the environment. Attaching to an environment sets system and environment variables so that the correct runtime and code is used in the execution of subsequent commands.

To attach to an environment:

- Make sure that you are logged in using the administration account for the desired environment, for example `splsys`.
- Execute the following command:

```
<SPLDIR>/<environment>/bin/splenvirion.sh -e <environment>
```

Or

```
<SPLDIR>\<environment>\bin\splenvirion.cmd -e <environment>
```

Where `<SPLDIR>` is the mount point defined for the product and `<environment>` is the name of the environment to access.

Note:

This command must be run before any UNIX-based command (including running the product background processes) to ensure that the correct environment is in place.

If you are running multiple versions of the product, ensure that you run the correct version of the `splenvirion[.sh]` utility for the environment by manually changing to the directory where the `splenvirion[.sh]` utility exists for the desired environment prior to running the command.

The following is an example of `splenviron.sh` execution:

```
$ /spl/DEMO/bin/splenviron.sh -e DEMO
Version ..... (SPLVERSION) : Vx.x.x
Environment Name ..... (SPLENVIRON) : DEMO
Environment Code Directory (SPLEBASE) : /spl/DEMO
App Output Dir - Logs ... (SPLOUTPUT) : /spl/sploutput/DEMO
```

The above example summary of the command illustrates that important environment variables and their values are set. Use this information to confirm that you have successfully attached to the correct environment.

3.3 Starting an Environment

To ensure a successful startup of the product the components should be started in the following order:

- The database server must be started according to local standards. This includes any communications software such as listeners to enable the product to communicate to the database. After starting the database server, the batch interface can be used.
- The Business Application Server must be started to enable the web application server to use the business objects and the business object conduit to accept web transactions.
- The web application server must be started to enable web clients to access the screens and business objects. After starting the Business Application Server and the web application server, the XAI incoming calls, the batch interface, and online users have access to the system.
- The end users can start the browser to access the product front-end screens.

3.3.1 Starting All Tiers on a Single Server

If the Business Application Server and web application server for an environment are on the same physical machine they can be started using the following set of tasks:

- Start the database using the utilities provided by the database vendor.
- Log on to the server containing the Web application server and/or Business application server using the administration account for the desired environment (for example, `splsys`).
- Execute the following command to attach to the desired environment:

Linux/UNIX:

```
<SPLDIR>/<environment>/bin/splenviron.sh -e <environment>
```

Windows:

```
<SPLDIR>\<environment>\bin\splenviron.cmd -e <environment>
```

Where `<SPLDIR>` is the mount point defined for software the environment and `<environment>` is the name of the environment to start.

- Start the Web application server, Business Application Server and MPL using the following command:

Linux/UNIX:

```
spl.sh start
```

Windows:

```
spl.cmd start
```

Refer to the [spl – Start/Stop Environment](#) for more options.

Note: As an alternative, it is possible to start the Web application server and business application tiers using the console or utilities provided with the J2EE Web application server software.

The script will display the startup messages as dictated by the J2EE Web application server vendor.

Note: If an unauthorized user attempts to execute this command the following error message – "...MUST be writable by admin userID" is output.

3.3.2 Starting/Stopping at Boot Time (UNIX/Linux)

One of the implementation questions that may arise is to start all the environments at UNIX/Linux boot time. This is possible by writing a script and placing it in `/etc/init.d` (or equivalent for your platform). A suggested standard is to provide a script that takes a parameter of start or stop. The script could then be used to start or stop product environments on the machine:

```
#!/usr/bin/ksh
#
# Purpose  : Start/Stop all copies of the product on a machine
#
Usage() {
echo "Usage :"
echo "  $0 [start|stop]"
exit 1
}
#-----
#
#####
#
# Main
# check command line arguments if [ "$#" -eq "0" ]
then
Usage exit 1
fi
# Loop through all environments in /etc/cistab
if [ ! -f /etc/cistab ]
```

```
then
echo  "/etc/cistab  file  does  not  exist.  Product  is  not  installed
correctly"
exit 1
fi
cat  /etc/cistab  |  while  IFS=:  read  _env  _filler1  _splebase  _splapp
_fill2
_start do
#  Only environments with the start parameter set to Y should be
started if [ ${_start} = "Y" ]
then
if [ -d ${_splebase} ]
then
# Determine owner of the environment
export OWNER='perl ${_splebase}/bin/getconfvalue.plx -k SPLUSER'
# Format start command
_startcmd="${_splebase}/bin/splenviron -e {_env} -c ""spl.sh start"""
_stopcmd="${_splebase}/bin/splenviron -e {_env} -c ""spl.sh stop"""
# Run command
case $1 in
"start") su - $OWNER -c "${_startcmd}" ;;
"stop") su - $OWNER -c "${_stopcmd}" ;;
*)  Usage
exit 1;;
esac
fi
fi
done
# Finished
```

Note: The above script is provided as a sample only. Use the above script as an example for any custom scripts to start the product at boot time.

3.3.2.1 What to Look for in Startup

As outlined in Common Application Logs the application logs all information to application logs during the startup, operation and shutdown of the application. These logs can be used to check that the startup of the product is successful. The logs contain the following sections for a startup (class indicates startup message):

- The Web Application is initialized (class = `web.startup.SPLWebStartup`) within the J2EE Web application server.
- Configuration Settings are loaded from the relevant configuration files (class = `shared.environ.ApplicationProperties`).
- The product is set to Production mode (this denotes Development versus Production settings) (class = `shared.context.ApplicationMode`). Most installations are Production mode. Only environments where the Oracle Utilities SDK is used will not be in Production mode.
- The state of compression is verified (class = `web.dynamicui.TransformServletHelper`).
- Refer to Web application server Configuration for details of this setting.
- The framework used by the product is initialized and settings within the framework are prepared to be loaded (class = `support.context.ContextFactory`).
- The metadata is loaded into memory for configuration control (class = `shared.context.ContextLoader`).
- Any checks for any customizations (class = `shared.environ.ContextManagedObjectSet`). In most cases, environments that do not have any product customizations will report a warning about a resource not loading. This can be ignored.
- Any lookups are loaded into memory (class = `support.context.ComponentContainerLookupHelper`). Lookups are metadata used to enumerate valid values for flags, common values etc.
- Additional metadata is loaded into memory (class = `support.context.ContextFactory`).
- The metadata used to configure the product includes entities, Code Descriptions, algorithms, batch controls, components and Change Handlers.
- Hibernate ORM mappings used by the product are loaded (class = `support.context.ApplicationContext`). The number of mappings will vary between releases and parts of the product that are used.
- The connection pool to the database is initialized according to the configuration settings (class *prefix hibernate.**). If the connection information is incorrect or the database is down the connection pool connection will retry (according to the configuration settings). If this is the case you will see the connection information and error messages, such as "**Connections could not be acquired from the underlying database!**" in this log.

Note: The messages seen will vary depending your database type and version.

- A successful database connection is shown in the message "Done building hibernate session" (class = `support.context.ApplicationContext`). A number of additional messages may appear as dictated by the database vendor to indicate versions and connectivity information.
- The database statement cache is initialized within the product (class = `support.sql.PreparedStatementImpl` and class = `support.context.CacheManager`).
- The owner of the system is initialized. This identifies the application owner for implementation purposes. In all cases the implementation value is "CM" for Custom Modification. Other values are supported for Oracle internal use only.
- The Web application server/Business Application Server static cache is then loaded (class = `api.globalContext.GlobalContextHelper`) which includes:

- Preloading language settings (`class = web.startup.PreloadLoginInfo`). If preloading is *enabled* then the progress of preloading is shown on the startup log. Preloading ends with message "XSLT main preload" (`class = web.startup.PreloadLoginInfo`).
- Loading product based style sheets (XSL) for screen generation.
- Navigation Keys (for static menus and context sensitive menus) (`class = web.dynamicui.NavigationInfoCache`)
- Metadata is loaded as indicated (`class = support.context.CacheManager`)
- Service Interceptors are loaded (`class = api.serviceinterception.InterceptorRepository`)
- Menus are loaded (`class = domain.web.MenuLoginService`)
- Navigation information is loaded (`class = domain.web.SystemLoginInfoHelperService`)
- Service definitions are loaded (`class = service.metainfo.MetaInformationRepository`)
- Installation record defaults are loaded (`class = web.common.WebInstallationDataHelper`)
- If the online batch daemon is enabled then the daemon is loaded into memory and started (`class = grid.node.DistributedGridNode` and prefix `grid.space`). Any work to be detected will result in additional messages (`class = grid.node.WorkProcessor`).

Once *the application is loaded* the J2EE Web application server will indicate the product is available (the message for this varies – refer to the J2EE Web application server documentation for details).

3.4 Stopping an Environment

To ensure a successful shut down of the product the components should be stopped in the following order:

- The end users should shut down the browser containing the product front-end screens.
- The MPL must be shutdown (if used) to prevent outgoing XAI transaction from being processed.
- The Web application server must be shutdown to disable web clients' access to the system. After the web application server is shutdown, end users do not have access to the system but batch processes may still run.
- The Business Application Server must be shutdown to disable the Web application server completely.
- The database server must be shut down according to local standards. This includes any communications software such as listeners to enable the product to communicate to the database. At this point all users (batch and online) do not have access to the environment.

3.4.1 Stopping All Tiers on a Single Server

If the Business Application Server and web application server for an environment are on the same physical machine they can be stopped/shutdown using the following set of tasks:

- Log on to the server containing the Web application server and/or Business application server using the administration account for the desired environment (for example, splsys).
- Execute the following command to attach to the desired environment:

Linux/UNIX:

```
<SPLDIR>/<environment>/bin/splenvirion.sh -e <environment>
```

Windows:

```
<SPLDIR>\<environment>\bin\splenvirion.cmd -e <environment>
```

Where <SPLDIR> is the mount point defined for software the environment and <environment> is the name of the environment to stop.

- Stop the Web application server, Business Application Server and MPL using the following command:

Linux/UNIX:

```
spl.sh stop
```

Windows:

```
spl.cmd stop
```

Refer to the `spl[.sh]` utility for more options.

Note: As an alternative, it is possible to stop the Web application server and business application tiers using the console or utilities provided with the J2EE Web application server software.

The script will display the shutdown messages as dictated by the J2EE Web application Server vendor.

- Stop the database using the utilities provided by the database vendor.

3.4.1.1 What to Look for in Shutdown Messages

As outlined in Common Application Logs the application logs all information to application logs during the startup, operation and shutdown of the application. These logs can be used to check that the shutdown of the product is successful. The logs contain the following sections for a shutdown (class indicates message class used):

- If the online batch daemon was enabled, it is shutdown (*classes = grid.node.OnlineGridNode, grid.node.DistributedGridNode, grid.space.SpaceManager, grid.space.TaskScheduler, grid.space.TaskScheduler and grid.space.ThreadPool*). The "**Thread pool shutting down**" message indicates a successful shutdown.
- The Web application server/Business Application Server applications are asked to shutdown (*class = web.startup.SPLWebStartup*).
 - JMX connectors to the product are shutdown
 - The Application Context within the J2EE Web application server is shutdown.
- Database connections are closed (*class = hibernate.impl.SessionFactoryImpl*).
- Application shutdown is complete when the message "*(web.startup.SPLWebStartup) Application Context shutdown successfully*" is displayed.

3.5 Starting and Stopping Using consoles

The last section uses supplied utilities to stop and start embedded mode installations. If the native mode installation is used then there are a number of ways to start and stop the product:

- Logon to the Oracle WebLogic Administration console for the domain and navigate to the servers section where the product is installed. Using the Control function, start or stop the servers as necessary.

Note: This facility also allows enabling or disabling Administration Mode for a server. This allows administration tasks on that server while disabling end user access.

- For customers using Oracle Enterprise Manager, logon to the Oracle Enterprise Manager console the product can be started and stopped using the following target types:
 - WebLogic Domain
 - WebLogic Server for product servers
 - Domain Application Deployment¹⁰
- For customers using the Application Management Pack for Oracle Utilities¹¹ the product can be started and stopped using the following target types:

¹⁰ While it is possible to start and stop at the individual application deployment it is not recommended to maintain overall availability.

- Oracle Utilities Environment - Starts and Stops all child targets in a single operation.
- Oracle Utilities Web Application
- Oracle Utilities Web Services
- Oracle Utilities Batch Server

¹¹ Customers using the Application Management Pack for Oracle Utilities should use the WebLogic targets as additional features such as blackouts and brownouts are supported in those targets.

4. Monitoring

This section outlines some basic monitoring regimes and methods for the product. It is highly recommended that you read the *Oracle Utilities Application Framework Performance Troubleshooting Guides* (Doc ID: 560382.1) on [My Oracle Support](#).

During monitoring you are typically looking for unusual activity and seeing if the current configuration of the product can handle the peaks and troughs of usage.

Unusual activity is activity that is not representative of the normal activity. For example, maybe during a marketing campaign the call center traffic doubles. This would be regarded unusual activity. At this point the current configuration may not be configured to handle the traffic so the problem needs to be identified and the configuration changed to cater for the new load.

Also during normal operations underlying problems may surface in the form of long running transactions, increases in error rates (in logs and timeouts) or runaway transactions. Runaway transactions are transactions that seem to be looping. These can be caused by data inconsistencies or bugs. Most of them are due to an unusual combination of data entries.

Some customers collect usage information to identify and analyze unusual activity. This is known as Site Profiling, Capacity Planning or Availability Planning. This is typically Proactive activity.

The product stores usage information within the database that can be extracted for this purpose. This section outlines the methods and techniques you can use to extract this information reactively and proactively.

4.1 Monitoring Regimes

Typically the art of monitoring is the collection and analysis of various pieces of information and then making changes to the configuration to address any issues or problems that occur.

With the various monitoring facilities available in the product a combination that is valid for the site becomes a monitoring regime for that site. Typically, monitoring regimes pick up trends in the business or traffic volumes that require changes to the configuration. As part of the implementation of the product the monitoring regime for your site should be determined.

Typically the monitoring regimes that are chosen fall into a number of categories:

- **Reactive** - Monitoring for any exception after it happens and making changes to the configuration to prevent the exception from occurring again. This is the most common regime adopted by IT groups. The only problem with this approach is that you have to experience potentially threatening outages before stabilization happens.
- **Proactive** - Setting monitoring tolerances so that exception conditions are recognized before they happen and making configuration changes to prevent them from happening. This is also known as Problem Anticipation or Problem Prevention. This is the goal of most of the IT groups to ensure high availability.
- **Mixed** - This is a mixture of pro-active and re-active regime. This is not uncommon.

4.2 Monitoring Client Machines

The product's front end is the Microsoft Internet Explorer browser. Typically any Internet Explorer or operating system monitoring specified by Microsoft can be performed against the client to yield performance information.

While collecting this information can be performed using various tools, it is usually not applicable in all monitoring situations unless the client machine is below the specification outlined in the *Oracle Revenue Management and Billing Installation Guide* for the platform and version of the product you are using. The browser collection points specified here are typically the ones that are more applicable to the product than all of the available ones for the client.

Refer to the Microsoft documentation on how to fully monitor a client machine for performance information

4.2.1 Monitoring the Desktop

One of the areas that customers tend to monitor is the desktop client. Typically this involves using tools provided by Microsoft (and other vendors) to collect typical statistics, such as CPU, disk activity, memory usage and network usage. It is possible to monitor the client using the following tools:

- **Desktop vendor tools** (Performance Monitor) – The Performance Monitor (located in the "Administration Tools" menu from Windows) is a starting point for monitoring the client. Refer to Microsoft documentation on what aspects of a client machine to monitor.
- **Network Monitor** (*netMon* or other) – Windows Server includes a network capture facility that is handy to locate problems on a client machine. Alternatives are available such as Ethereal etc.
- **Network Latency** - Network tools like *ping* and *traceroute* measure latency by determining the time it takes a given network packet to travel from source to destination and back, the so-called round-trip time. Round-trip time is not the only way to specify latency, but it is the most common. Inconsistent ping times or long ping times can indicate network issues.
- **Bandwidth Saturation levels** - A number of tools exist for computer networkers to measure the bandwidth of network connections. On LANs, these tools include *netperf* and *ttcp*.
- **Packet Loss** - Packet loss is when data packets appear to be transmitted correctly at one end of a connection, but never arrive at the other. This might be because:
 - Network conditions are poor and the packet became damaged in transit.
 - The packet was deliberately dropped at a router because of congestion.
- Packet loss can be detected from the client PC using *netstat* and calculating the percentage of the *Segments Sent* that become *Segments Retransmitted*.

Note: Ping and traceroute also include packet loss statistics.

- **Failed Connection Attempts** - When the client and/or server cannot accept a connection it generates a Failed Connection Attempt on either the client or the server (or both). A large number of Failed Connection Attempts can indicate networking or capacity issues on the client or server. The most common cause is that the accept queue on the network parameters (usually on the network cards) is full, and there are some requests waiting on the sync queue (usually on the network card).

4.2.2 Client Debug Facility

Before a problem is to be registered with Oracle support, the transaction that caused the problem should be traced to help support solve the issue quickly. A debug facility is provided within the product to help capture this additional information.

Logging of debug information can be set at a global level or at a local level. The global debug setting is not recommended for a production system as it reduces overall performance and therefore is not covered in this document.

The local level enables you to navigate to the problem area and then to switch debugging on for that individual user to recreate the problem. You can then collate the debug information to be sent to support.

To use this facility you must specify an additional parameter at the end of the URL. For example:

`http://<host>:<port>/<server>/cis.jsp?debug=true`

Where,

Command Line Option	Description
<code><host></code>	Web Application Server hostname
<code><port></code>	Port allocated to product installation
<code><server></code>	Context for the product at installation time

Note: For the user to have debug access their User ID must have "Change" access to service F1DEBUG.

After the debug control menu is displayed, you navigate to the screen where the problem is encountered and then enable *Global Debug* by *toggling* the checkbox on. To turn off *Global Debug*, *toggle* the check box off. It is recommended to select *Trace All* for effective tracing. The other options are used by Developers only. The trace information is written to the **spl*.log** in the `$SPLSYSTEMLOGS` (`%SPLSYSTEMLOGS%` in Windows).

Note: The product uses `spl_web.log` and `spl_service.log` but `spl_service.log` or may not appear depending on the installation type, therefore the name `spl*.log` is used.

Debug allows specific information to be logged:

- **Client Data** – Data presented to the browser. This pops up an additional window displaying the object as it is built.
- **Server Data** – Data presented to the server. This pops up an additional window displaying the object as it is received by the server.
- **Trace time** – Include time tracing in the log.
- **COBOL buffers** (if COBOL is used), Debug List Info, Debug Filter and Grid Display Time – Used for development to display internal information and filter for specific information. It is recommended that these options should not be used unless performing development.
- **Trace All** – Enable all trace modes below except Trace SQL Parameters.
- **Trace Output** – Dump output from all calls
- **Trace SQL** – Dump SQL statements

- **Trace SQL Parameters** – Dump all result sets (Warning: This is not recommended for production systems as it will result in performance degradation.)
- **Program Start** – Write a record for ever module start
- **Program End** – Write a record for ever module end

Most tracing in non-development uses *Trace All* unless otherwise instructed by Oracle Support. All debug information is written to the `spl*.log` files.

4.2.2.1 Steps to Using the Debug Facility

To use the debug facility you follow the process:

- Add `?debug=true` to your URL for the product. This will display the debug toolbar on the browser screen as shown below:
 -



Figure 10: Debug Toolbar

- **Start Debug** – Start the logging of the transaction.
- **Stop Debug** – Stop the logging process
- **Show Trace** – Show trace information (Configuration based objects only)
- **Clear Trace** – Clear Trace Information
- **Show User Log** – Show debug information for the user (line limit is configurable).
- **Validate on DB** – SDK Use only
- **Global Debug** – Set debug level.
- **JS Console** – Enable JavaScript console
- Select *Global Debug* to specify the level of debug information. This will display the *Debug Control* window where you should ensure that *Trace All* is selected. Other options should only be used if instructed by Oracle Support. A sample of the Debug Control dialog is shown below:




Figure 11: Debug Controls

- Navigate to the transaction that you wish to trace as a user would normally operate. Press "Start Debug" to initiate debug.
- Run the transaction that you want to trace and to recreate the issue. While you work the trace information is written to the log files.
- Deselect *Global Debug* or press *Stop Debug* so that debugging is disabled. This will stop debug code writing to the writing to the log. If you select *Show User Log* the log lines output by the debug facility are displayed (*up to the line limit specified*). This will only show lines applicable to the Current User only.

Note: If the User ID is shared across multiple physical users then the information may contain debug information from multiple sessions.

4.3 Monitoring Web/Business Application Server

There are a number of methods that are available for monitoring a Web Application from a J2EE Web application server:

- **Java Management Extensions (JMX)** – Most Web application servers expose JMX Management Beans (MBeans) to allow JMX browsers to view and use this information. Java 7 has a predefined set of MBeans that can be enabled automatically.
- **Web application server console** – All Web Application Servers offer a web based console that provides both administration and basic monitoring functions. These are usually sufficient for spot real time checking of tolerances and basic monitoring. Some console use calls to JMX API's provided by the Web application server vendor and built into Java 7 (and above).
- **Oracle Enterprise Manager** - Customers using Oracle WebLogic can use the Fusion Middleware targets available within Oracle Enterprise Manager to monitor online and web services applications. Customers using Application Management Pack for Oracle Utilities can use monitoring capabilities of those targets as well.

- **Command Based Utilities** – Apart from the console, most Web application server vendors offer a command line utility to extract performance information (or perform administration). Most console utilities call JMX MBeans and provide a command line interface into JMX that can be used natively.
- **Log-based monitoring** – Most Web application servers provide standardized logs that can be analyzed using consoles, log monitors or simple scripts.
- **Native OS utilities** – Most operating systems are becoming java aware and provide OS and Java monitoring from OS monitoring facilities.

Refer to the *Oracle Utilities Application Framework Performance Troubleshooting Guides* (Doc ID: 560382.1) on [My Oracle Support](#) for details of monitoring aspects of the product.

4.4 JMX Based Monitoring

With the advent of Java Management Extensions (JMX) technology into base java, it is possible to use the technology to monitor and manage java infrastructure from a JSR160 compliant JMX compliant console (or JMX browser). Whilst the J2EE components of the product can use basic JMX statistics such as Memory usage, Threads, Class information and VM summary information, there are application specific JMX classes added to the product to allow greater levels of information to be display and additional operations.

The Oracle Utilities Application Framework has implemented a set of product specific JMX classes on the Web Application Server and Business Application Server tiers of the architecture to allow the following:

- Management of the cache of the Web Application Server. See **Server Cache Management** for more details of this cache.
- Collection of JVM information and performance statistics for memory, thread usage and operating system level information. Most of these are extensions of `java.lang.management` classes.
- Collection of service based performance information for SLA tracking on the Business Application Server.

To use this facility the facility must be configured and enabled to allow the collection of the relevant information. This can be done at installation time by using the following configuration settings:

Configuration Setting	Deployment Details
<code>WEB_JMX_RMI_PORT_PERFORMANCE</code>	Port Number used for JMX based management for Web Application Server.
<code>ouaf.jmx.splwlsg.base.support.management.mbean.JVMInfo</code>	Globally enable or disable <code>JVMInfo</code> Mbean (setting in <code>spl.properties</code>). Default is enabled.
<code>ouaf.jmx.com.splwg.base.web.mbean.s.FlushBean</code>	Globally enable or disable <code>FlushBean</code> Mbean (setting in <code>spl.properties</code>). Default is enabled.
<code>ouaf.jmx.com.oracle.ouaf.uws.mbeans.WSFlushBean</code>	Globally enable or disable <code>WSFlushBean</code> Mbean (setting in <code>spl.properties</code>). Default is enabled.

Configuration Setting	Deployment Details
BSN_JMX_RMI_PORT_PERFORMANCE	Port Number used for JMX based management for Business Application Server.
ouaf.jmx.com.splwg.ejb.service.management.PerformanceStatistics	Globally enable or disable PerformanceStatistics Mbean (setting in spl.properties). Default is enabled.
BSN_JMX_SYSUSER	Default JMX UserID for both Web Application Server and Business Application Server.
BSN_JMX_SYSPASS	Default JMX Password for both Web Application Server and Business Application Server.
BATCH_RMI_PORT BATCH	Port Number used for JMX based management for background processing.
WEB_BATCH_CLUSTER_URL BATCH	Cluster URL override to be used for JMX based management for background processing. This can manually be set to identify an administration node for processing.

These settings are registered in the **ENVIRON.INI** for setting in the relevant configuration files. It is important that the values used for these port numbers are unique across all environments within a particular machine. The security used for these ports are defined as outlined in the **JMX Security** section of this document.

4.4.1 Web Application Server JMX Reference

Once configured a JMX client (e.g. jconsole) can be used to connect to the JMX information using the following Remote Connection string:

```
service:jmx:rmi:///jndi/rmi://<host>:<jmx_port>/oracle/ouaf/webAppConnector
```

Where,

- <host>: The Web Application Server host name
- <jmx_port>: The JMX Port specified using `WEB_JMX_RMI_PORT_PERFORMANCE` from the `ENVIRON.INI` configuration file.

The credentials provided to the JMX console are as configured in `JMX Security`. Upon successful connection to the JMX port and host with the correct credentials provides access to the Mbean information.

The figure below illustrates the successful connection to the JMX Mbeans using jconsole (as an example):




Figure 12: Web Application Server Mbeans in jconsole Example

The structure of the Mbean is shown in the figure below:




Figure 13: Web Application Server Mbeans

The following table summarizes the Mbean attributes and operations for the Web Application Server:

Mbean	Arguments	Usage
BaseMasterBean		Master MBean
Attributes		
NumberofMbeans	None	Returns number of active Mbeans
MBeanList	None	Returns an array with the list of Mbeans defined to this Master Mbean.
Operations		
disableMbean	Mbean Name	Disables Mbean with designated name as a par
enableMbean	Mbean Name	Enables Mbean with designated name
disableMbean	None	Returns a list with the list of Mbeans defined to this BaseMasterBean. Names can be programmatically used to supply parameters to disableMbean and enableMbean.
enableJVMSystemBeans	None	Enables base JVM system Mbeans

Mbean	Arguments	Usage
disableJVMSystemBeans	None	disables base JVM system Mbeans
FlushBean	Manages Online Cache	
Attributes		
VersionInfo	None	Returns string of base version number of Flush Mbean.
CompleteClassPath	None	Returns classpath name of Flushbean Mbean.
FlushBean (Refer to Server Cache for details of this cache).		
Operations		
flushAll	None	Reset all elements in online data cache
flushDropDownCache	None	Resets cached elements of the online drop down lists in online data cache
flushDropDownField	None	Resets drop down fields in online data cache (Development use only)
flushFieldAndFKMetaData	None	Resets Field and Foreign Key Meta Data in online data cache
flushMenu	None	Reset Menu items in online data cache
flushMessageCatalog	None	Reset field labels in online data cache
flushMessaging	None	Reset messages in online data cache
flushNavigationInfo	None	Reset navigation information in online data cache
flushPortalMetaInfo	None	Reset portal and zone information in online data cache
flushSystemLoginInfo		Reset security information in online data cache
flushUIXSLs	None	Reset user interface style sheets in online data cache.
JVMInfo	JVM Information Mbean	
Attributes		
CompleteClassPath	None	Displays the class path of the JVMInfo mbean.
JVMInfo		

Mbean	Arguments	Usage
Operations		
classPath	None	Returns the full classpath used by the online JVM
systemSettings	None	Returns the attributes of the JVM for debugging and support purposes.
JVMSystem		JVM Mbean (Java base metrics)
ClassLoadingMXBean	Class Loading JVM Mbean	
Attributes		
LoadedClassCount	None	Returns the number of classes that are currently loaded in the JVM
ObjectName	None	The ObjectName for uniquely identifying the MXBean for the class loading system within an MBeanServer. In this case it is set to java.lang:type=ClassLoading
TotalLoadedClassCount	None	Returns the total number of classes that have been loaded since the JVM was last started.
UnloadedClassCount	None	Returns the total number of classes unloaded since the Java virtual machine has started execution.
Verbose	None	Enables or disables the verbose output for the class loading system. Default is false (disabled)
MemoryMXBean		Memory JVM Mbean
Attributes		
HeapMemoryUsage	None	Returns the current memory usage of the heap that is used for object allocation. Initial, Committed, Maximum and Used memory statistics are provided for Heap memory
NonHeapMemoryUsage	None	Returns the current memory usage of non-heap memory that is used by the JVM. Initial, Committed, Maximum and Used memory statistics are provided for Non-Heap memory
ObjectPendingFinalization	None	Returns the approximate number of objects for which finalization is pending (used for diagnosing memory leaks).

Mbean	Arguments	Usage
ObjectName		The ObjectName for uniquely identifying the MXBean for the memory system within an MBeanServer. In this case it is set to java.lang:type=Memory
Verbose	None	Enables or disables the verbose output for the memory system. Default is false (disabled).
MemoryMXBean		
Operations		
gc	None	Initiate garbage collection
MemoryMXBean		
Notifications		
javax.management.Notification	None	Used for low memory notifications. Notification Types supported: (java.management.memory.threshold.exceeded, java.management.memory.collection.threshold.exceeded)
OperatingSystemMXBean		Operating System Mbean
Attributes		
MaxFileDescriptorCount	None	Returns the File Descriptor Maximum Limit in force on the JVM
OpenFileDescriptorCount	None	Returns the number of Open File Descriptors currently used by JVM
CommittedVirtualMemorySize	None	Returns the amount of committed virtual memory (that is, the amount of virtual memory guaranteed to be available to the running process).
FreePhysicalMemorySize	None	Returns the total amount of free physical memory
FreeSwapSpaceSize	None	Returns the total amount of free swap space
ProcessCpuTime	None	Returns the amount of process CPU time consumed by the JVM
TotalPhysicalMemorySize	None	Returns the total amount of physical memory
TotalSwapSpaceSize	None	Returns the total amount of swap space

Mbean	Arguments	Usage
Name	None	Returns the operating system name
Version	None	Returns the version of the operating system
Arch	None	Returns the operating system architecture
AvailableProcessors	None	Returns the number of available processors to the JVM
SystemLoadAverage	None	Returns the system load average for the last minute.
Name	None	Returns the name representing the running JVM. The returned name string can be any arbitrary string and a JVM implementation can choose to embed platform-specific useful information in the returned name string. Each running virtual machine could have a different name.
ClassPath	None	Returns the Java class path that is used by the system class loader to search for class files.
ObjectName	None	The ObjectName for uniquely identifying the MXBean for the operating system within an MBeanServer. In this case it is set to <code>java.lang:type=OperatingSystem</code>
RuntimeMXBean Attributes		Java Runtime MBean
Attributes		
Starttime	None	Returns the start time of the Java virtual machine in milliseconds. This method returns the approximate time when the JVM started.
ManagementSpecVersion	None	Returns the version of the specification for the management interface implemented by the running JVM.
VmName	None	Returns the Java virtual machine implementation name.
VmVendor	None	Returns the Java virtual machine implementation vendor.
VmVersion	None	Returns the Java virtual machine implementation version.

Mbean	Arguments	Usage
SpecName	None	Returns the Java virtual machine specification name.
SpecVendor	None	Returns the Java virtual machine specification vendor.
SpecVersion	None	Returns the Java virtual machine specification version.
LibraryPath	None	Returns the Java library path
BootClassPath	None	Returns the boot class path that is used by the bootstrap class loader to search for class files.
Uptime	None	Returns the uptime of the Java virtual machine in milliseconds.
BootClassPathSupported	None	Tests if the JVM supports the boot class path mechanism used by the bootstrap class loader to search for class files. Returns false if not supported; true if supported.
InputArguments	None	Returns the input arguments passed to the JVM which does not include the arguments to the main method. This method returns an empty list if there is no input argument to the JVM. Typically, not all command-line options to the 'java' command are passed to the Java virtual machine. Thus, the returned input arguments may not include all command-line options.
SystemProperties	None	Returns a map of names and values of all system properties.
ThreadMXBean Attributes		
ThreadCount	None	Returns the current number of live threads including both daemon and non-daemon threads
PeakThreadCount	None	Returns the peak live thread count since the JVM started or peak was reset.
TotalStartedThreadCount	None	Returns the total number of threads created and also started since the JVM started.

Mbean	Arguments	Usage
DaemonThreadCount	None	Returns the current number of live daemon threads.
ThreadContentionMonitoringSupported	None	Tests if the JVM supports thread contention monitoring. Returns <i>false</i> if not supported; <i>true</i> if supported.
ThreadContentionMonitoringEnabled	None	Enables or disables thread contention monitoring. Set to <i>false</i> to disable; <i>true</i> to enable.
CurrentThreadCpuTime	None	Returns the total CPU time for the current thread in nanoseconds. The returned value is of nanoseconds precision but not necessarily nanoseconds accuracy. If the implementation distinguishes between user mode time and system mode time, the returned CPU time is the amount of time that the current thread has executed in user mode or system mode.
CurrentThreadUserTime	None	Returns the CPU time that the current thread has executed in user mode in nanoseconds. The returned value is of nanoseconds precision but not necessarily nanoseconds accuracy.
ThreadCpuTimeSupported	None	Tests if the JVM supports CPU time measurement for the current thread. Returns <i>false</i> if not supported; <i>true</i> if supported.
ThreadCpuTimeEnabled	None	Enables or disables thread CPU time measurement. The default is platform dependent. Set to <i>false</i> to disable; <i>true</i> to enable.
CurrentThreadCpuTimeSupported	None	Tests if the Java virtual machine supports CPU time measurement for the current thread. Returns <i>false</i> if not supported; <i>true</i> if supported.
ObjectMonitorUsageSupported	None	Tests if the Java virtual machine supports monitoring of object monitor usage. Returns <i>false</i> if not supported; <i>true</i> if supported.
SynchronizerUsageSupported	None	Tests if the JVM supports monitoring of ownable synchronizer usage. Returns <i>false</i> if not supported; <i>true</i> if supported.

Mbean	Arguments	Usage
AllThreadIds	None	Returns all live thread IDs. Some threads included in the returned array may have been terminated when this method returns.
ObjectName	None	The ObjectName for uniquely identifying the MXBean for the java runtime within an MBeanServer. In this case it is set to java.lang:type=Runtime
ThreadMXBean		
Operations		
dumpAllThreads	Locked Monitors, Locked Synchronizers	<p>Returns the thread info for all live threads with stack trace and synchronization information. Some threads included in the returned array may have been terminated when this method returns.</p> <ul style="list-style-type: none"> • Locked Monitors- if <i>true</i>, dump all locked monitors. • Locked Synchronizers- if <i>true</i>, dump all locked ownable synchronizers.
findDeadlockedThreads	None	Finds cycles of threads that are in deadlock waiting to acquire object monitors or ownable synchronizers. Threads are deadlocked in a cycle waiting for a lock of these two types if each thread owns one lock while trying to acquire another lock already held by another thread in the cycle.
getThreadCpuTime	Thread Id	Returns the total CPU time for a thread of the specified ID in nanoseconds. The returned value is of nanoseconds precision but not necessarily nanoseconds accuracy. If the implementation distinguishes between user mode time and system mode time, the returned CPU time is the amount of time that the thread has executed in user mode or system mode.
getThreadInfo	Thread Id	Returns the thread info for a thread of the specified id with no stack trace.

Mbean	Arguments	Usage
getThreadInfo	Array of Thread Ids	Returns the thread info for each thread whose ID is in the input array ids with no stack trace.
getThreadInfo	Thread Id, maxDepth	Returns thread information for a thread of the specified id, with stack trace of a specified number of stack trace elements. The <i>maxDepth</i> parameter indicates the maximum number of <i>StackTraceElements</i> to be retrieved from the stack trace. This method does not obtain the locked monitors and locked synchronizers of the thread.
getThreadInfo	Array of Thread Ids, maxDepth	Returns the thread information for each thread whose ID is in the input array ids, with stack trace of a specified number of stack trace elements. The <i>maxDepth</i> parameter indicates the maximum number of <i>StackTraceElements</i> to be retrieved from the stack trace. This method does not obtain the locked monitors and locked synchronizers of the threads.
getThreadInfo	Array of Thread Ids, locked Monitors, locked Synchronizers	Returns the thread info for each thread whose ID is in the input array ids, with stack trace and synchronization information. This operation obtains a snapshot of the thread information for each thread including: <ul style="list-style-type: none"> the entire stack trace, the object monitors currently locked by the thread if <i>lockedMonitors</i> is true, and the ownable synchronizers currently locked by the thread if <i>lockedSynchronizers</i> is true
getThreadUserTime	Thread Id	Returns the CPU time that a thread of the specified ID has executed in user mode in nanoseconds.
resetPeakThreadCount	None	Resets the peak thread count to the current number of live threads.
OEMTargetsBean	Application Management Pack for Oracle Utilities interface	

Mbean	Arguments	Usage
Operations		
toXML	None	Generate Target information for Oracle Enterprise Manager. An XML document with information for the Application Management Pack for Oracle Utilities.

4.4.2 Business Application Server JMX Reference

Once configured a JMX client (e.g. `jconsole`) can be used to connect to the JMX information for the Business Application Server using the following Remote Connection string:

```
service:jmx:rmi:///jndi/rmi://<host>:<jmx_port>/oracle/ouaf/ejbAppConnector
```

Where,

Command Line Option	Description
<code><host></code>	The Business Application Server host name.
<code><jmx_port></code>	The JMX Port specified using BSN_JMX_RMI_PORT_PERFORMANCE from the ENVIRON.INI configuration file.

The credentials provided to the JMX console are as configured in JMX Security. Upon successful connection to the JMX port and host with the correct credentials provides access to the Mbean information. The figure below illustrates the successful connection to the JMX Mbeans using jconsole (as an example):




Figure 14: Business Application Server Mbeans in jconsole Example

The structure of the Mbean is shown by the figure below:




Figure 15: Business Application Server Mbeans

The following table outlines the Mbean attributes and operations for the Business Application Server:

Mbean	Arguments	Usage
PerformanceMBeanController		Performance Mbean Controller
Operations		
disableMbean	None	Disable PerformanceStatistics Mbean
enableMbean	None	Enable PerformanceStatistics Mbean
PerformanceStatistics		Performance Statistics
Attributes		
ReadCount	None	Returns number of executed <i>read object</i> calls since last reset or last time collection enabled.
DeleteCount	None	Returns number of executed <i>delete object</i> calls since last reset or last time collection enabled.
ChangeCount	None	Returns number of executed <i>change object</i> calls since last reset or last time collection enabled.
AddCount	None	Returns number of executed <i>add object</i> calls since last reset or last time collection enabled.
DefaultItemCount	None	Returns number of executed calls to <i>default the object values</i> since last reset or last time collection enabled.
ExecuteBOCount	None	Returns number of calls to <i>Business Objects</i> since last reset or last time collection enabled.
ExecuteBSCount	None	Returns number of calls to <i>Business Services</i> since last reset or last time collection enabled.
ExecuteListCount	None	Returns number of calls to <i>List based services</i> since last reset or last time collection enabled.
ExecuteSearchCount	None	Returns number of calls to <i>search based services</i> since last reset or last time collection enabled.
ReadSystemCount	None	Returns number of calls to <i>Oracle Utilities Application Framework system Objects</i> since last reset or last time collection enabled.
ValidateCount	None	Returns number of calls to <i>Validate objects</i> since last reset or last time collection enabled.
ExecuteSSCount	None	Returns number of calls to <i>Service Scripts</i> since last reset or last time collection enabled.
PerformanceStatistics		
Operations		
CompleteClassPath	None	Returns the class path used for the Mbeans.

Mbean	Arguments	Usage
reset	None	Resets statistical values. See Resetting Statistics section for more advice on this operation.
maxTime	Service Name	Returns maximum (worst case) time, in ms, for the designated service since the last reset or last time collection enabled.
minTime	Service Name	Returns minimum (best case) time, in ms, for the designated service since the last reset or last time collection enabled.
completeExecutionDump	None	Returns complete statistics for all services executed since the last reset or last time collection enabled. See Execution Dump section for details of format.
avgTime	Service Name	Returns average time, in ms, for the designated service since the last reset or last time collection enabled.
executionInfo	Service Name	Returns complete statistics for the designated service executed since the last reset or last time collection enabled. See Execution Dump Format section for details of format.
calledServices	None	Returns list of services and service types since the last reset or last time collection enabled. See Service Lists section for details of format.
ProbeTransactionMbean		Component Probe
Operations		
checkApplicationServer	None	Constructs HTTP/HTTPS request and returns RFC2616 HTTP response code and response time in ms
checkDatabaseConnectivity	None	Executes SQL SELECT to test database connectivity. Returns response time in ms.
checkBusinessApplicationServer	None	Executes base service (read only) to return application server performance in ms.
OEMTargetsBean		Application Management Pack for Oracle Utilities interface
Operations		
toXML	None	Generate Target information for Oracle Enterprise Manager. An XML document with information for the Application Management Pack for Oracle Utilities.

Note: The times quoted in the statistics only record times experienced from the Business Application Server down to the data and back. They do not include network time to the Web Application Server, any time spent by the Web Application Server, network time to the browser client or browser rendering times. The Business Application Server time represents the typical majority of the time spent in a transaction.

4.4.3 Batch JMX Reference

Once configured a JMX client (e.g. jconsole) can be used to connect to the JMX information for the Business Application Server using the following Remote Connection string:

service:jmx:rmi:///*jndi/rmi://<host>:<jmx_port>/oracle/ouaf/batchConnector*

Where:

Command Line Option	Description
<host>	A Batch Server host name
<jmx_port>	The JMX Port specified using BATCH_RMI_PORT from the ENVIRON.INI configuration file.

Note: In a multi-host environment, it is possible to reserve a specific host/port combination using the WEB_BATCH_CLUSTER_URL which specifies a specific host and BATCH_RMI_PORT combination as the administration machine.

The credentials provided to the JMX console are as configured in JMX Security. Upon successful connection to the JMX port and host with the correct credentials provides access to the Mbean information. The figure below illustrates the successful connection to the JMX Mbeans using jconsole (as an example):




Figure 16: Batch Server Mbeans in jconsole Example




Figure 17: Batch Thread Mbean in jconsole Example

The structure of the Mbean is shown by the figure below:




Figure 18: Batch Server Mbeans

The following table outlines the Mbean attributes and operations for the Business Application Server:

Mbean	Usage
BatchCluster	Cluster Mbean for cluster with name <ClusterName>
Attributes	
Address	Cluster address as specified in COHERENCE_CLUSTER_ADDRESS in ENVIRON.INI
Name	Name of the Cluster as specified in COHERENCE_CLUSTER_NAME in ENVIRON.INI
Port	Port number assigned to Cluster as specified in COHERENCE_CLUSTER_PORT in ENVIRON.INI
ClusterAsString	XML representation of the cluster for use with Application Management Pack for Oracle Utilities. The structure represents the hierarchy of JMX calls in XML format.

Mbean	Usage
Operations	
flushAllCaches	Flush the data reuse cache across the batch cluster. Invoke this operation to reload configuration data changes for batch jobs.
registerClusterMBeans	Register the Mbeans for lower level tracking. This needs to be invoked to allow threadpool and batch thread level tracking.
unregisterClusterMBeans	Disable lower level tracking. This stops low level tracking.
ThreadPools ¹²	Threadpool Statistics (an entry per threadpool)
Attributes	
Name	Name of Threadpool
AvailableThreads	Number of spare threads for batch processes. A value of zero (0) indicates the threadpool is at capacity. Note: For cache or administration threadpools, this value is always zero (0).
NumberOfMembers	Number of members/hosts defined to the threadpool. A value of zero (0) indicates a cache or administration threadpool.
Members	Member (submitters/nodes) statistics
Attributes	
Hostname	Name of Host hosting this threadpool instance
JVMName	Name of JVM assigned at runtime
PID	Unique OS Process Id for JVM
MemberId	Member Number. This number is unique across the cluster and is used to track the member internally by the framework.
Info	Parameters used to start threadpool instance in free format. This is primarily used by Application Management Pack for Oracle Utilities.
Operations	
flushAllCaches	Flush the cache for this instance

¹² This tree will only appear if registerClusterMbeans is executed to enable the additional metrics.

Mbean	Usage
stopNode	Stop this member. This allows members to be stopped manually.
displayClusterCache	Cluster Cache in free format. This is primarily used by Application Management Pack for Oracle Utilities.
ClusterNode	Member information about the member you are connected to
Attributes	
JVMName	Name of JVM assigned at runtime
PID	Unique OS Process Id for JVM
Info	Parameters used to start threadpool instance in free format. This is primarily used by Application Management Pack for Oracle Utilities.
Operations	
flushAllCaches	Flush the cache for this instance
stopNode	Stop this member. This allows members to be stopped manually.
displayClusterCache	Cluster Cache in free format. This is primarily used by Application Management Pack for Oracle Utilities.
BatchThread/BatchJob ¹³	Batch Thread/Job Metrics
Attributes	
BatchCd	Batch Code
BatchNumber	Batch Number
CancelRequested	True if the thread has been asked to stop running. See CancelRequestedBy.
CancelRequestedBy	If CancelRequested=true, this will be a string indicating the workstation from where the cancellation was requested. This value will also be logged to the Batch Run Tree.
DateTimeStarted	The date and time the batch process was started.
DistThreadPool	The thread pool to which this batch process belongs.
ElapsedTime	How long the batch process has been running in java format

¹³ BatchThreads is spawned per thread. BatchJob is spawned for jobs with multiple threads as a control node. BatchJob will not be spawned for single thread jobs.

Mbean	Usage
ExecutionStrategyClass	This indicates the commit strategy followed by the program
JMXInfo	Additional Tags for batch thread
LanguageCD	Language Code used for execution for messages
MaxExecutionAttempts	MAX-ERROR value
MaximumCommitRecords	Commit Interval for Timeouts (Legacy Support only)
MaximumTimeoutMinutes	Timeout Interval (Legacy Support only)
ProcessDate	Business Date
ProgramName	The program name executed. This is set on the Batch Control.
ProgramType	The program type. Value is typically: Java
RecordsCommitted	The number of record updates that have been committed to the database. See note below.
RecordsInError	The number of records so far in error. This is what will be logged to the Batch Run Tree. See note below.
RecordsProcessed	The number of records processed so far. This is what will be logged to the Batch Run Tree. See note below.
RerunNumber	Rerun Number if RunType is Rerun.
RunType	The type of run: New Run, Restart or Rerun.
SoftParameters	List of job parameters from Batch Control.
Status	Current status of the thread. Valid values are: "Initializing" (at the start of execution to the call to getJobWork in the application class); Getting Work means it is currently in the process of selecting the work units for the batch process; Got Work means it is has successfully selected the work and is in the process of initiating the threads.
ThreadCount	Thread Limit
ThreadNumber	Thread Number
TraceProgramEnd	Whether tracing for Program End is enabled
TraceProgramStart	Whether tracing for Program Start is enabled
TraceSQL	Whether SQL statement tracing is enabled
TraceStandardOut	Whether output tracing is enabled
UserID	User used for authorization

Mbean	Usage
WorkUnitSize	The total number of work units for this batch process. For new and restarted runs, this will always contain the total number of work units as selected in the getJobWork method when the batch process was originally started.
WorkUnitSizeThisRun	This is the number of work units for this particular run. For a restarted run, this value will typically be less than the above value; otherwise they will be the same.
WorkUnitsCommitted	The number of work units that have had their work committed.
WorkUnitsInError	The work units that have been found to be in error so far.
WorkUnitsProcessed	The work units that have been processed so far.
Operations	
cancelThread	Cancel this thread. This updates CancelRequested and CancelRequestedBy. Information is persisted on the Batch Run Tree.
OEMTargetsBean	Application Management Pack for Oracle Utilities interface
Operations	
toXML	Generate Target information for Oracle Enterprise Manager. An XML document with information for the Application Management Pack for Oracle Utilities.

Note:

Each batch thread is uniquely identifiable in the BatchThread JMX call with the name <mbean>.<batchcd>.<thread>_of_<threadlimit>.<javathread>. Where <mbean> is BatchJob or BatchThread, <batchcd> is the batch control identifier for the job, <thread>_of_<threadlimit> is the thread within thread limit and <javathread> is the internal java thread number.

The "Records..." numbers are what will be used to log to the Batch Run Tree, and they are usually in step with the "WorkUnits..." values. The reason they are shown separately is because it is possible for custom background processes manually manipulate the record counts for the Batch Run Tree. The true progress status of a thread is reflected in the "WorkUnits..." counts.

4.4.4 JMX Security

By default, when JMX is enabled for Web Application Server, Web Service, or Business Application Server then a default JMX configuration using simple security is implemented as outlined in <http://java.sun.com/javase/6/docs/technotes/guides/management/agent.html>.

The simple security system consists of two files that control the access permissions and passwords specified by default for the installation:

Configuration Setting	Location of file	Template
Password File	scripts/ouaf.jmx.password.file	ouaf.jmx.password.file.template
Access Control File	scripts/ouaf.jmx.access.file	ouaf.jmx.access.file.template

These files are built by the `initialSetup` utility using the templates indicated. Refer to the templates or generated files for valid values. The format of these files is dictated by <http://java.sun.com/javase/6/docs/technotes/guides/management/agent.html#gdeup>.

Note: By default, the passwords stored in these files are in encrypted text. Alternative security schemes are allowed as documented in the link above. This will require a custom templates and changes to specific files to implement.

4.4.5 Extending JMX Security

Whilst the base installation of the product uses the basic level of security there are ways of extending the current security:

- If the default security scheme is sufficient for your needs then additional users may be manually added using the `user exits` for the above files.
- For production it is recommended to implement an SSL based solution as outlined in <http://docs.oracle.com/javase/6/docs/technotes/guides/management/agent.html>.

Refer to Oracle Revenue Management and Billing Security Guide for more schemes available for this process.

4.4.6 Execution Dump Format

In previous versions (V1.x) of the Oracle Utilities Application Framework based products, it was possible to extract performance information from the Business Application Server using a logging based method using the Oracle Tuxedo `txrpt` utility. This facility was useful in tracking performance of individual services over time to detect non-compliance against Service Level Agreement targets. With the advent of later versions of the Oracle Utilities Application Framework, the need for Oracle Tuxedo was removed but there was a need for performance information to be collated.

In the latest version of the Oracle Utilities Application Framework, it is possible to track performance information using JMX to process externally to check performance and check compliance against Service Level Agreements.

To extract the information from the product the following needs to be done:

- Use a JMX browser (or JMX console) product to connect to the Business Application Server JMX port using the appropriate credentials.
- Invoke the `completeExecutionDump` operation from the `PerformanceStatistics` Mbean. This will return a Comma separated values, with field names in the header record, containing the performance data which can be transferred to the clipboard (or whatever format supported by the JMX client). The format of the CSV is shown in the table below:

Column	Comment
ServiceName	Name of Service
ServiceType	Type Of Service or Action (see Service Lists section for valid values)
MinTime	Minimum Service Time, in ms, since last reset
MaxTime	Maximum Service Time, in ms, since last reset
Avg Time	Average Service Time, in ms, since last reset
# of Calls	Number of Calls to Service since last reset
Latest Time	The service time of the latest call, in ms
Latest Date	The date of the latest service call (in format: YYYY-MM- DD::hh-mm-ss-sss)
Latest User	The userID of the user who issued the latest call

- (Optionally) Invoke the `reset` operation from the `PerformanceStatistics` Mbean to reset the statistics for the next collection period. Refer to [Resetting Statistics](#) section for a discussion of this task.

This information can then be post processed in an appropriate analysis tool to determine appropriate actions.

Note: The statistics are active as long the Mbean is enabled or the system is active. Shutting down the Business Application Server with collection of the data may cause data loss for the statistics.

4.4.7 Service Lists

The JMX Performance Mbeans collect information about application services that have been executed during the collection period. This information can be obtained using the `calledServices` operation which returns a list of called services and their valid actions (summarized actions that have been called) in the format:

`<servicename> [<valid action>]`

Where,

Command Line Option	Description
<code><servicename></code>	Name of Service
<code><valid actions></code>	List of valid actions recorded for the service. The table below lists the valid values.

Valid Action	Comment
ADD	Service is attempting adding a new instance of an object to the system. For example, adding a To Do record.
CHANGE	Service is attempting changes to an existing object in the system.

Valid Action	Comment
DEFAULT_ITEM	Service is resetting its values to defaults. For example, by pressing the <i>Clear</i> button on the product UI toolbar.
DELETE	Service is attempting to delete an existing object
EXECUTE_BO	Service is a business object
EXECUTE_BS	Service is a business service
EXECUTE_LIST	Service is a list based service
EXECUTE_SEARCH	Service is a search
EXECUTE_SS	Service is a service script (including BPA scripts)
READ	Service is attempting to retrieve an object from the system
READ_SYSTEM	Service is a common Oracle Utilities Application Framework based service.
VALIDATE	Service is issuing a validation action

4.4.8 Resetting Statistics

The performance statistics collected represent values since the application was started or when it has been reset. Collection of statistics, without reset, can adversely influence the effectiveness of the statistics over time. It is therefore recommended to reset the statistics on a regular basis (after they are collected for example).

This can be achieved using the `reset` operation from the `PerformanceStatistics` Mbean to effectively zero or blank out the collection statistics.

For example, if the statistics are to be collected on an hourly basis then the reset should occur after the data collection happens per hour.

Note: Any statistics collected during the actual reset operation will not be reflected in the statistics. This situation should have minimal impact on overall statistics.

4.5 Database Connection Monitoring

By default, the product uses a common database User ID for accessing the information from the connection pools used by the product (via Universal Connection Pool (UCP)). While this sufficient for execution of the product, it can complicate monitoring individual connections and troubleshooting database issues with individual users or transactions.

It is now possible to show additional details that are inherited from the from the online and Web Services components. The following information is available from the connection and accessible from `v$session`.

Parameter	Online	Web Service	Batch
CLIENT_IDENTIFIER ¹⁴	UserID	UserID	UserID
MODULE	Service Name	Web Service Name	Batch Control
ACTION	Transaction Type	Transaction Type	Thread Number
CLIENT_INFO	Contents of Database Tag characteristic on User	"Web Service"	Threadpool Name

For example, the following database query will return the session ids and the users using them at any time:

```
SELECT sid, client_identifier, module, client_info, action FROM V$SESSION;
```

The new information can be used to track sessions using the v\$session view, use more advanced features of the database and use other database options.

4.6 Probe Transaction

One of the monitoring facilities in the product is a probe transaction for the online component of the product. This is a set of JMX calls to the various components of the architecture to determine two sets of metrics:

- Availability of the component - The availability will return a pass or fail on availability (including details is possible) of the component.
- Raw performance - The raw transaction performance of the component from the call.

This represents the raw performance and should be used as a raw indication of performance at the network level.

The following components are tested using this capability:

Component	Test	Availability	Performance
Web Application Server	HTTP/HTTPS ping	RFC 2616 code	Time in ms
Business Application Server	Service Call	true or false	Time in ms
Database Server	SQL SELECT	True or SQL Error	Time in ms

The API is part of the Business Application Server JMX facility.

Note: Customers using Application Management Pack for Oracle Utilities can use additional API's for performance and availability tracking.

¹⁴ Due to the length limitation on CLIENT_IDENTIFIER the value will be the authorization identifier not the authentication identifier.

5. Configuration

5.1 Configuration Files

There are a number of configuration files that are implemented across the various components of the environment.

5.1.1 application.xml – ADF Application Configuration

Note: This configuration file only applies to Oracle WebLogic and Oracle ADF implementations.

To use the Oracle Application Development Framework (ADF) integration the ADF components need to be deployed to a predefined ADF container. The definition of this container is controlled by the J2EE standard application.xml file.

Parameter	Context	Source
context-root	ADF context root used for calls	Set to WEB_CONTEXT_ROOT/adf
display-name	Specifies the application display name	Set to SPLAdf
web-uri	Defines location of WAR file	Set to SPLAdf

Example:

```

<?xml version = '1.0'?>
<application
  xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"
  xsi:schemaLocation="http://java.sun.com/xml/ns/javaee
  http://java.sun.com/xml/ns/javaee/application_5.xsd"
  xmlns="http://java.sun.com/xml/ns/javaee">
  <display-name>SPLAdf</display-name>
  <module>
    <web>
      <web-uri>SPLAdf</web-uri>
      <context-root>demo/adf</context-root>
    </web>
  </module>
</application>

```

Note: This file should not be altered unless instructed by Oracle Support.

5.1.2 cistab - Global Configuration Files

The `cistab` file is a key configuration file for both the Web application server and the database application server. It is built during the installation process and is used by the product administration utilities to ensure that any output or log files generated by the product are stored in the correct location. It holds the mount points (e.g. directories) used during the installation of the product to hold the product and its log files.

Location of `cistab` file:

Linux/UNIX:

`/etc/cistab`

Windows:

`c:\spl\etc\cistab`

A sample `cistab` file is outlined below:

```
DEV:::/spl/DEV:/spl/sploutput/DEV::N
DEMO:::/spl/DEMO:/spl/sploutput/DEMO::N
TEST:::/spl/TEST:/spl/sploutput/TEST::N
TEST2::d:\spl\TEST2:e:\sploutput\TEST2::N
```

The format of the file is described below:

Position	Usage
1	Environment Name – specified at installation time. It is in UPPER case.
2	Reserved for future use.
3	Directory for the product software and configuration files (the <code>SPLEBASE</code> environment variable definition).
4	Directory for the product output files (the <code>SPLOUTPUT</code> environment variable definition).
5	Reserved for future use.
6	This flag may be used in custom start up scripts to indicate whether to start the environment at system boot time. Valid values are Y or N. This is the only setting that should be altered after installation.

Warning: Do not alter the `cistab` file unless instructed to do so by Oracle support personnel unless otherwise directed.

Note: For Windows environments it is possible to move the file to alternative drive by setting `%SYSTEMDRIVE%` to an alternative drive prior to running any utilities. For example `set SYSTEMDRIVER=D:` places the `cistab` in `d:\spl\etc`.

5.1.3 coherence-cache-config.xml - Oracle Coherence Configuration

BATCH

The `coherence-cache-config.xml` configuration file is used by the CLUSTERED mode of execution to manage the Oracle Coherence based cache across the batch cluster. This file is generally not altered at the implementation level as it is preconfigured to execute the batch component of the product.

For details of the contents of this file refer to the [Oracle Coherence Integration Guide](#).

5.1.4 e0Batch.properties - General Batch Properties

Note: This configuration file is generated and should not be altered unless instructed by Oracle Support.

This configuration file is used by the batch component to set the location of the installation and the location for any log files generated by the batch component.

This configuration file has two settings that are generated from the `e0Batch.properties.template` file located in `templates` directory.

Configuration Setting	Contents
<code>standalone.dir</code>	Location of batch installation
<code>SPLOUTPUT</code>	Location of output files

5.1.5 ejb-jar.xml - Enterprise Java Server Beans Configuration

The Business Application Server and MDB functionality uses Enterprise Java Server beans to implement service calls. By default the behavior of these components is defined and controlled with the `ejb-jar.xml` configuration file.

This configuration file is generated by the `initialSetup` using the `templates/ejb-jar.xml.template` file.

Note: This configuration file is typically NOT altered unless custom JMS or MDB resources are to be included in the servers within the product. Typically JMS resources are not included in the server. Refer to the [Oracle WebLogic JMS Integration](#) (Doc ID: [1308181.1](#)) whitepaper for details of JMS or MDB advanced configuration.

5.1.6 ENVIRON.INI - Environment Configuration File

The `ENVIRON.INI` file is used by the Web application server and the Business Application Server to define the environment and provide the basis for starting and stopping the environment. The file is created during the installation process and is used to generate other files. This file is maintained using the `configureEnv` utility provided in the installation.

Warning: Do not alter the `ENVIRON.INI` manually. Always use `configureEnv` utility because additional configuration files depend on the settings in this file. If the configurations mismatch, improper operation of the product may occur.

Location of ENVIRON.INI file:

Linux/UNIX:

\$SPLBASE/etc/ENVIRON.INI

Windows:

%SPLBASE%\etc\ENVIRON.INI

The file contents are in text format and are of the form:

<parameter>=<value>

Where,

- <parameter>: Name of configuration parameter
- <value>: Value of the configuration parameter

For example:

```
...appViewer=appViewer
DBCONNECTION=jdbc:oracle:thin:@myserver:1521:train
DBDRIVER=oracle.jdbc.driver.OracleDriver
DBNAME=TRAIN
...
...
```

The settings contained in the ENVIRON.INI file are outlined in Appendix - ENVIRON.INI.

5.1.6.1 Extracting Information from ENVIRON.INI for Scripts

It is possible to write your own calls to the ENVIRON.INI using the same utilities used by the product to get values of configuration parameters for your own utilities. Do not hardcode values that can be obtained from ENVIRON.INI.

To obtain values of parameters use the command line:

Linux/UNIX:

perl \$SPLBASE/bin/getconfvalue.plx -k <parameter>

Windows:

perl %SPLBASE%\bin\getconfvalue.plx -k <parameter>

Where,

Command Line Option	Description
<parameter>	Name of configuration parameter from ENVIRON.INI you desire to get the value of.

For example:

ENVIRON.INI content:

...
DBNAME=TRAIN
...

Example call:

```
$ export DB='perl $SPLBASE/bin/getconfvalue.plx -k DBNAME'  
$ echo $DB  
TRAIN
```

Note: If the value is NOT set or the key is invalid the value of the call is null or blank.

5.1.7 hibernate.properties - Database Connectivity Settings

Opening a connection to a database is generally much less expensive than executing an SQL statement. A connection pool is used to minimize the number of connections opened between application and database. It serves as a librarian, checking out connections to application code as needed. Much like a library, your application code needs to be strict about returning connections to the pool when complete, for if it does not do so, your application will run out of available connections. Hence, the need for having a connection pooling mechanism such as Hibernate using Oracle [Universal Connection Pool](#) (UCP) connection pooling or JNDI based connection pooling.

The online and Web Service components of the product use JNDI based connection pools and the batch component uses UCP based connection pools.

Hibernate is a powerful Object Relational Mapping (ORM) technology that makes it easy to work with relational databases. Hibernate makes it seem as if the database contains plain Java objects, without having to worry about how to get them out of (or back into) database tables. Coupled with the UCP or JNDI connection pooler, it provides a comprehensive connectivity tool for the COBOL/java to operate effectively against the database.

The product uses the Hibernate and either JNDI or UCP libraries to create a connection pool and connect the java/COBOL objects to the database to store, update, delete and retrieve data. It is used for all the database access for online as well as batch.

Refer to <http://hibernate.org/> for more information on the technology aspects of Hibernate.

The product has a configuration file for the database connectivity and pooling called the hibernate.properties configuration file. This file contains the configuration settings for the database connections and the connection pool to be used by any of the SQL statements accessing the database.

The configuration settings contained in the hibernate.properties file are summarized in the hibernate.properties section.

For a more indepth description of these parameters and others not included with the product see <http://hibernate.org/>.

5.1.8 log4j.properties – Product Logging Configuration

Note: This log file should not be altered unless specified. The generated configuration file has all the recommended settings for all sites.

The product uses the log4j Java classes to centralize all log formats into a standard format. The details of the configuration settings and log4j itself are available at <http://logging.apache.org/log4j/> or <http://en.wikipedia.org/wiki/Log4j>.

5.1.9 Server Jar File (ouaf_jar_versions.txt)

Note:

This configuration file is used for internal purposes and should not be altered unless instructed to do so by Oracle Support.

Additional external jar files used for customizations do not need to be added to this file. This is used for base product verification only.

The java component of the product uses a number of industry standard jar files that are provided or used by the product. The `etc/ouaf_jar_versions.txt` lists the jar file that is used and the required version used by the version of the product installed. This file is used at installation and runtime for integrity checks. If you wish to determine what version of an external jar is used then refer to this information file.

5.1.10 spl.properties – Product Behaviour Settings

The product Web Application has a specific number of settings outside of the J2EE specification to control the internals of the product. This file exists as similar files exist for all modes of operation of the product (for example, Batch can be run outside the J2EE Web application server). Because of this a common configuration standard was adopted:

For a description of all settings in the `spl.properties` file refer to the `spl.properties` parameter descriptions.

5.1.11 submitbatch.properties - Submitter Configuration BATCH

Note: This is the default configuration file. Refer to the [Configuring Batch using bedit](#) section for a discussion of the role of this configuration and its variations

Each background process requires a configuration file to control its behavior. There are two levels of files that control the individual batch job executions:

- [submitbatch.properties](#) - This file sets the global settings for all batch jobs that are submitted. This file is located in `$SPLBASE/splapp/standalone/config` directory (or `%SPLBASE%\splapp\standalone\config` on Windows)
- `<batchcode>.properties` - This file is the same format as [submitbatch.properties](#) but contains any job specific settings and/or overrides to settings in the [submitbatch.properties](#).

Note: Any command line options can override settings in any configuration file.

This file is generated using the [bedit](#) facility.

5.1.12 tangosol-coherence-override.xml - Coherence Overrides

BATCH

The [tangosol-coherence-override.xml](#) configuration file is used by the CLUSTERED mode of execution to override the settings for the Oracle Coherence based cache across the batch cluster. This file is generally not altered at the implementation level as it is preconfigured to execute the batch component of the product.

This file is generated using the [bedit](#) facility.

For details of the contents of this file refer to the [Oracle Coherence Integration Guide](#).

5.1.13 threadpoolworker.properties - Threadpool Configuration

BATCH

Note: This is the default configuration file. Refer to the Configuring Batch using bedit section for a discussion of the role of this configuration and its variations

Each threadpoolworker requires a configuration file to control its behavior. This file is generated using the bedit facility for each type of threadpoolworker.

Note: Any command line options on threadpoolworker[.sh] utility can override settings in any configuration file.

This file is generated using the bedit facility.

5.1.14 web.xml – J2EE Deployment Descriptor

Note: For Inbound Web Services, a resource version of this file is generated.

The Web deployment descriptor editor lets you specify deployment information for modules created in the Web development environment.

The information appears in the web.xml file. The web.xml file for a Web project provides information necessary for deploying a Web application module. It is used in building a WAR/EAR file from a project.

The Web Application is controlled by a configuration file that holds behavioral information for the applications. Refer to <http://jcp.org/en/jsr/detail?id=109> for more details of the format. For example:

...

```
<env-entry>
  <description>Value of HTTP 1.1 max-age header parameter for
  JSPs</description>
  <env-entry-name>maxAge</env-entry-name>
  <env-entry-value>28800</env-entry-value>
  <env-entry-type>java.lang.Integer</env-entry-type>
</env-entry>
<env-entry>
  <description>How long to cache drop down values in seconds</description>
```

```
<env-entry-name>fieldValuesAge</env-entry-name>
<env-entry-value>3600</env-entry-value>
<env-entry-type>java.lang.Integer</env-entry-type>
</env-entry>
<env-entry>
<description>Is this a development environment</description>
<env-entry-name>isDevelopment</env-entry-name>
<env-entry-value>false</env-entry-value>
<env-entry-type>java.lang.Boolean</env-entry-type>
</env-entry>
<env-entry>
<description>Preload ALL Pages</description>
<env-entry-name>preloadAllPages</env-entry-name>
<env-entry-value>false</env-entry-value>
<env-entry-type>java.lang.Boolean</env-entry-type>
</env-entry>
<env-entry>
<description>Disable preloading of Pages</description>
<env-entry-name>disablePreload</env-entry-name>
<env-entry-value>false</env-entry-value>
<env-entry-type>java.lang.Boolean</env-entry-type>
</env-entry>
```

...

For application specific entries refer to the web.xml parameter descriptions.

Note: It is highly recommended that you do not change this configuration file by extracting the configuration file from the WAR/EAR file using Java utilities, making the change manually and rebuilding the WAR/EAR file. Use initialSetup to build the WAR/EAR file as documented in Web application server Configuration Process

5.1.15 weblogic.xml – Oracle WebLogic Extensions

Note:

This configuration file only applies to Oracle WebLogic implementations.

For Inbound Web Services, a resource version of this file is generated.

For backward compatibility with Oracle WebLogic environments, an additional Oracle WebLogic configuration file `weblogic.xml` is generated and used to influence the Oracle WebLogic Server to exhibit additional behavior.

Parameter	Context	Source
<code>context-root</code>	The <code>context-root</code> element defines the context root of this stand-alone Web application. If the Web application is part of an EAR, not stand-alone, specify the context root in the EAR's <code>web.xml</code> file. A <code>context-root</code> setting in <code>web.xml</code> takes precedence over <code>context-root</code> setting in <code>weblogic.xml</code> .	Defaults from template
<code>java-charset-name</code>	Specifies the Java character set to use.	Defaults from template (UTF-8)
<code>page-check-seconds</code>	Determines the interval at which a server checks to see if JSP files in a Web application have changed and need recompiling. Used for development	Derived from <code>WEB_WLPAGECHECKSECONDS</code> parameter from <code>ENVIRON.INI</code>
<code>prefer-web-inf-classes</code>	Loading of web classes from the WEB-INF are loaded in preference to system or Oracle WebLogic classes. Defaulted to false.	Defaults from template
<code>resource-path</code>	A path which, if included in the URL of a request, signals Oracle WebLogic Server to use the Java character set specified by <code>java-charset-name</code> .	Defaults from template
<code> servlet-reload-check-secs</code>	Defines whether an Oracle WebLogic Server will check to see if a servlet has been modified, and if it has been modified, reloads it. The -1 value tells the server never to check the servlets, 0 tells the server to always check the servlets, and the default is to check each 1 second. A value specified in the console will always take precedence over a manually specified value.	Defaults from template

Parameter	Context	Source
url-rewriting-enabled	<p>Provides methods for configuring a J2EE web application that is deployed on an Oracle WebLogic Server instance. Oracle WebLogic Server instantiates this interface only when you deploy a web application.</p> <p>This interface can configure web applications that are deployed as a WAR file or an exploded directory.</p>	Defaults from template (false)

Note: This configuration file is not usually altered by an implementation as it applies to development (SDK) platforms only. It is documented for completeness here.

Example:

```

<weblogic-web-app xmlns="http://www.bea.com/ns/weblogic/90">
  <session-descriptor>
    <url-rewriting-enabled>false</url-rewriting-enabled>
  </session-descriptor>
  <jsp-descriptor>
    <page-check-seconds>43200</page-check-seconds>
  </jsp-descriptor>
  <container-descriptor>
    <servlet-reload-check-secs>-1</servlet-reload-check-secs>
    <prefer-web-inf-classes>true</prefer-web-inf-classes>
  </container-descriptor>
  <charset-params>
    <input-charset>
      <resource-path>/*</resource-path>
      <java-charset-name>UTF-8</java-charset-name>
    </input-charset>
  </charset-params>
  <context-root>/</context-root>
</weblogic-web-app>

```

5.1.16 weblogic-ejb-jar.xml - WebLogic Extensions for Enterprise Java Server Beans

WebLogic Server-specific EJB deployment descriptor that contains elements related to WebLogic Server features such as clustering, caching, and transactions. This file is required if your beans take advantage of WebLogic Server-specific features.

This file is coupled with the [ejb-jar.xml](#) configuration file using the standard [weblogic-ejb-jar.xml](#) schema. This configuration file is generated by the initialSetup using the templates/weblogic-ejb-jar.xml.template file.

Note: This configuration file is typically NOT altered unless custom JMS or MDB resources are to be included in the servers within the product. Typically JMS resources are not included in the server. Refer to the [Oracle WebLogic JMS Integration](#) (Doc ID: [1308181.1](#)) whitepaper for details of JMS or MDB advanced configuration.

5.1.17 webservices.xml.resource - Web Services Configuration

Note: This file is automatically generated and should not be altered manually unless instructed by Oracle Support.

When using Inbound Web Services, a web services deployment descriptor, webservices.xml, must be generated to inform the J2EE Web Application Server of the Web Services.

This file is automatically generated from the template file webservices.xml.resource.iws.template located in the templates directory.

5.2 Web Browser Configuration

The product is browser based (browsers, versions and platforms are documented in the *Oracle Revenue Management and Billing Installation Guide* for your platform. Additionally the following settings are applicable to the browser:

- **Microsoft Internet Explorer** - Cache settings need to be *Every visit to the page* or *Automatically*. For non-production it is recommended to be set to *Every visit to the page* or *Automatically*. For production it is recommended to be set to *Automatically* to fully exploit performance caching. For example:




Figure 19: Internet Explorer Cache Settings

- **Mozilla Firefox/ Google Chrome** - Use the default settings with the browser.

Note: Clearing the cache upon exit will clear the cached screens of the product as well.

- In Microsoft Internet Explorer¹⁵, the product requires support for the HTTP 1.1 protocol to support compression and client cache management.

¹⁵ This does not apply to Mozilla FireFox and Google Chrome.




Figure 19: HTTP 1.1 Settings

Note: If a network proxy is used then "Use HTTP 1.1 through proxy connections" may need to be selected as well.

- The product uses Java scripting for user interactivity therefore Scripting of Java Applets (IE) in security settings, Allow sites to run Javascript (Chrome) in Content Settings and javascript.enabled (Firefox)¹⁶ in about:config must be set to true.



The screenshot shows the Firefox 'about:config' page with a search bar containing 'javascript'. A red box highlights the 'javascript.enabled' preference, which is listed in the table below. The table has columns for 'Preference Name', 'Status', 'Type', and 'Value'. The 'javascript.enabled' entry has a 'default' status, a 'boolean' type, and a 'true' value.

Preference Name	Status	Type	Value
browser.urlbar.filter.javascript	default	boolean	true
javascript.enabled	default	boolean	true
javascript.options.asmjs	default	boolean	true
javascript.options.baselinejit	default	boolean	true

¹⁶ By default, Firefox and Chrome enable Javascript automatically.




Figure 20: Javascript Settings

- The product uses popup windows for searches; therefore popup blockers should be configured to allow popups from the product Web application server hosts. Add the Application URL by adding an exception using the relevant function in the browser¹⁷. For example:





Figure 21: Popup Blocker Configuration

- Set your browser cache size to a reasonable size to hold the cached pages as needed.

¹⁷ Some browsers allow users to add an exception at runtime. Refer to the browser documentation for more information.

5.3 Web Application Server Configuration

5.3.1 Caveat

The product supports a number of J2EE Web application servers. Each J2EE Web application server is configured differently and has additional options (clustering, logging etc) that can be used. This document is written neutral to the differences of each J2EE Web application server. Refer to the documentation provided with the J2EE Web application servers for the location of specific configuration settings discussed in this section as well as advanced settings supported.

5.3.2 Web Application Server Concepts

Each Web application server has a number of levels and each uses different terminology. The following "neutral" terminology will be used:

- The software exists on a physical machine.
- An installation of the Web Application Software is called an instance. Typically one instance of the software exists on a machine but you can have more than one installed.
- Within an instance you can define a server. This is also called a Java "container" which will house one or more J2EE applications. You will have at least one server per environment. A server uses one Java Virtual Machine (JVM).
- Within a server is the J2EE application. It can be a single J2EE application or multiples depending on the Web application server supported.

The Web application server you use may have different terminology for these same concepts. For the remainder of this section we will use the above terminology.

5.3.3 Web Applications

The product is deployed as a set of Web applications within the Web applications server:

- **root** – This is the product itself is installed.
- **XAIApp** – This is the Web services adapter component.

Note: XAI will be replaced by Inbound Web Services. Customers using XAI should migrate to Inbound Web Services. For a discussion of this process refer to Migrating from XAI to IWS (Doc ID: 1644914.1) available from [My Oracle Support](#).

- **appViewer** – An Application Viewer which contains a data dictionary and source viewer.
- **help** – Online Help.
- **MCPApp** – Mobile Connection Platform (**MOB** only)

Each of these J2EE Web Applications has its own configuration files and are combined together when the product is "built" into a WAR/EAR file by the initialSetup utility.

5.3.4 Web Application Server Configuration Files

Within each J2EE Web Application within the J2EE Web application server has its own configuration files. These files are typically embedded within the WAR/EAR files deployed with the product following the J2EE specification. In terms of configuration, the product structure within the WAR/EAR file looks like the following:




Figure 22: Configuration File Hierarchy

Configuration File	Contents
application.xml	Application Specifics MOB
hibernate.properties	Database connectivity
log4j.properties	Logging configuration
spl.properties	Behavior configuration
web.xml	Deployment Descriptor
weblogic.xml	WebLogic extensions

5.3.4.1 Web Application Server Configuration Process

To configure the Web application server during the installation process and post-installation then the following process should be used:




Figure 23: Web Application Server Configuration Process

- The configureEnv utility is used during installation time and can be used post implementation to set parameters in the ENVIRON.INI. If any parameters are derived or set from the ENVIRON.INI (see Source column in the relevant section) then the configureEnv utility should be used to maintain them.

Note: The configureEnv utility should be used to make any changes to the ENVIRON.INI. Manual changes to this configuration file are not recommended.

- After the ENVIRON.INI has been set or altered, the settings must be reflected in the relevant configuration files used by the Web application server by running the initialSetup utility:
 - web.xml
 - log4j.properties
 - spl.properties
 - application.xml
 - weblogic.xml
- The utility uses the templates from the templates directory to create substituted copies of these files in a standard location. The table below lists the configuration file, the templates used from the templates directory and the final configuration built during the initial configuration process:

Configuration File	Destination
Online Application (root)	
web.xml Template: web.xml.template	Linux/UNIX: \$SPLEBASE/etc/conf/WEB-INF Windows: %SPLEBASE%\etc\conf\WEB-INF
spl.properties Template: spl.properties.template	Linux/UNIX: \$SPLEBASE/etc/conf/root/WEB-INF/classes Windows: %SPLEBASE%\etc\conf\root\WEB-INF\classes
log4j.properties Template: log4j.properties.template	Linux/UNIX: \$SPLEBASE/etc/conf/root/WEB-INF/classes Windows: %SPLEBASE%\etc\conf\root\WEB-INF\classes
weblogic.xml Template: weblogic.xml.template	Linux/UNIX: \$SPLEBASE/etc/conf/root/WEB-INF Windows: %SPLEBASE%\etc\conf\root\WEB-INF
Web Services Adapter (XAIApp)	
web.xml (web.xml.XAIApp) Template: web.xml.XAIApp.template	Linux/UNIX: \$SPLEBASE/etc/conf/WEB-INF Windows: %SPLEBASE%\etc\conf\WEB-INF
spl.properties Template: spl.properties.XAIApp.template	Linux/UNIX: \$SPLEBASE/etc/conf/XAIApp/WEB-INF/classes Windows: %SPLEBASE%\etc\conf\XAIApp\WEB-INF\classes

Configuration File	Destination
log4j.properties Template: log4j.properties.XAIApp.template	Linux/UNIX: \$SPLEBASE/etc/conf/XAIApp/WEB-INF/classes Windows: %SPLEBASE%\etc\conf\XAIApp\WEB-INF\classes
weblogic.xml Template: weblogic.xml.XAIApp.template	Linux/UNIX: \$SPLEBASE/etc/conf/XAIApp/WEB-INF Windows: %SPLEBASE%\etc\conf\XAIApp\WEB-INF
Application Viewer (appViewer)	
web.xml (web.xml.appViewer) Template: web.xml.appViewer.template	Linux/UNIX: \$SPLEBASE/etc/conf/WEB-INF Windows: %SPLEBASE%\etc\conf\WEB-INF
weblogic.xml Template: weblogic.xml.appViewer.template	Linux/UNIX: \$SPLEBASE/etc/conf/appViewer/WEB-INF Windows: %SPLEBASE%\etc\conf\appViewer\WEB-INF
Help Application (help)	
web.xml (web.xml.help) Template: web.xml.help.template	Linux/UNIX: \$SPLEBASE/etc/conf/WEB-INF Windows: %SPLEBASE%\etc\conf\WEB-INF
weblogic.xml Template: weblogic.xml.help.template spl.properties Template: spl.properties.ohelp.template	Linux/UNIX: \$SPLEBASE/etc/conf/help/WEB-INF Windows: %SPLEBASE%\etc\conf\help\WEB-INF Linux/Unix: \$SPLEBASE/etc/conf/ohelp Windows: %SPLEBASE%\etc\conf\ohelp
MCP Application (MCApp) MOB	
web.xml (web.xml.MCApp) Template: MWM_web.xml.MCApp.template	Linux/UNIX: \$SPLEBASE/etc/conf/WEB-INF Windows: %SPLEBASE%\etc\conf\WEB-INF

Configuration File	Destination
spl.properties Template: MWM_spl.properties.MCPApp.template	Linux/UNIX: \$SPLEBASE/etc/conf/MCPApp/WEB-INF/classes Windows: %SPLEBASE%\etc\conf\MCPApp\WEB-INF\classes
log4j.properties Template: MWM_log4j.properties.MCPApp.template	Linux/UNIX: \$SPLEBASE/etc/conf/MCPApp/WEB-INF/classes Windows: %SPLEBASE%\etc\conf\MCPApp\WEB-INF\classes
SPLAdf Application (ADF Integration)	
application.xml (application.xml.SPLAdf) Template: MWM_application.xml.SPLAdf.template	Linux/UNIX: \$SPLEBASE/etc/conf/WEB-INF Windows: %SPLEBASE%\etc\conf\WEB-INF
weblogic.xml (weblogic.xml.SPLAdf) Template: MWM_weblogic.xml.SPLAdf.template	Linux/UNIX: \$SPLEBASE/etc/conf/WEB-INF Windows: %SPLEBASE%\etc\conf\WEB-INF

- At this point you may perform manual changes to the above files to parameters not implemented in the ENVIRON.INI.

Note: Any manual changes are overwritten after running the initialSetup utility unless the change is reflected in the appropriate template (see [Implementing Custom Templates](#) for more information). Backups should be made of any changes and then manually reapplied to reinstate all manual changes.

- To reflect configuration changes into the product Web Applications the initialSetup utility with the -w option must be executed. This will build the necessary WAR/EAR files to be deployed into the J2EE Web application server. This step is optional if configuration overrides are in use.

Depending on the architecture, the initialSetup will generate one or more EAR files. Refer to [Business Application Server Configuration](#) for a description of the EAR files.

At this point the product Web Applications are ready for deployment into the J2EE Web application server.

5.3.5 Quick Reference Guide for Web Application Server Configuration

To make configuration changes to the Web Application Server component of the product uses the following Quick Reference Guide to identify which process should be used:

- If the change is to any setting contained in the ENVIRON.INI for the Web Application Server then you must run the following utilities in the order indicated:
 1. Execute the configureEnv utility to reflect the parameter change in the ENVIRON.INI.

2. Execute the initialSetup utility (with the `-t` option) to rebuild the configuration files using the ENVIRON.INI and provided template files. This will reset the configuration to the contents of the base template files or custom template (if used).
3. Any configuration changes that are overridden by templates (base or custom) must be manually reapplied (if necessary).
4. Execute the initialSetup utility (with the `-w` option) to implement the configuration files in the product Web Application Server files. This step is not necessary if you are using configuration overrides.

- If the change is to any setting not contained in the ENVIRON.INI for the Web application server but is in the configuration files for the Web Application Server then you must run the following utilities in the order indicated:
 1. Make any manual changes to the relevant configuration files.
 2. Execute the initialSetup (with the `-w` option) utility to implement the configuration files in the product Web Application Server files. This step is not necessary if you are using configuration overrides.
- If native installation is used, it is recommended to redeploy or update the generated EAR files from the relevant command or console.

5.3.6 User Interface Backward Compatibility Settings

The following settings (in the `spl.properties` file) are used for backward compatibility of the User interface for customers upgrading from an Oracle Utilities Application Framework V2.1 based product (values of true emulate V2.1 user interface behavior for UI Maps):

- `spl.runtime.compatibility.uiMapDisableInputValue` – By default, if the XML schema has an input value with a default then setting this value to false will cause the product to set this value to blank and ignore the default value for add mode in all UI Maps. Setting of this value to true will cause the default to be displayed in the input field for add mode in all UI Maps. The default value for this parameter is false.
- `spl.runtime.compatibility.uiMapDropdownSelectFirstValue` – By default, dropdown widgets on UI Maps are defaulted to no value to force the user to select a value. By setting this parameter to true, forces all dropdowns on all UI Maps to automatically default to the first value in the dropdown list. By setting this value to false, the default, the UI Maps will have blank values as the default value for the dropdowns.
- `spl.runtime.compatibility.uiMapDisableTitle` – By default UI Maps contain a rendered title section. By setting this parameter to true, the title sections for all UI Maps are not automatically rendered. By setting this parameter to false, the default, title sections are rendered automatically for all UI Maps.
- `spl.runtime.compatibility.uiMapDisableGenerateUniqueHtmlIDs` – By default screen elements have unique ids for reference, including individual records in lists or queries. By setting this value to false, the default, the framework will generate unique ids for ADA compliance. If customizations from past releases have issues with these unique ids then setting the value to true will revert to behavior available in past releases of the product.

Note: It is recommended to leave the default value, false, for these parameters unless otherwise required or instructed by Oracle Support.

5.3.7 Web Application Server Deployment Process

After the configuration of the Web Application is complete (as outlined in Web Application Server Configuration Process) the final step to implement the product technically is to deploy the product within the J2EE Web application server.

There are three methods of deploying the product within the J2EE Web application server:

1. Use the deployment utilities provided on the console of the J2EE Web application server. The WAR/EAR files that are available under \$SPLEBASE/splapp/applications (or %SPLEBASE%\splapp\applications for Windows) can be manually deployed using the console. Refer to the Oracle Revenue Management and Billing Installation Guide for specific platform instructions and the administration guide for the J2EE Web application server.

Note: This is the only method that can be used if virtual Web application servers are used with the product.

2. Use the deployment utilities provided on the command line of the J2EE Web application server. The WAR/EAR files that are available under \$SPLEBASE/splapp/applications (or %SPLEBASE%\splapp\applications for Windows) can be manually deployed using the command line utilities supplied with your J2EE Web application server. Refer to the Oracle Revenue Management and Billing Installation Guide for specific platform instructions and the administration guide for the J2EE Web application server.
3. A number of specific utilities for J2EE Web applications are provided with the product to deploy the Web Application to the J2EE Web application server. These call the same utilities provided in Option 2 but are provided with the product.

Note: This section will outline Option 3 only.

A number of utilities are provided in the bin directory of the product to deploy the product to the J2EE Web application server. These utilities are outlined below:




Figure 24: Web Application Server Deployment Process

- For the IBM WebSphere or IBM WebSphere ND platform, use the `initialSetup` utility (with the `-d` or `-y` options) utility. This will call the relevant IBM WebSphere utility to perform the deployment.

Note: The `-y` option allows for a decoupled installation on IBM WebSphere. On Oracle WebLogic the console may be used to configure individual elements to achieve the same functionality.

- For Oracle WebLogic, there are two options:
 - Native Mode - Use the WebLogic console or WLST to deploy/redeploy the EAR files.
 - Embedded Mode - No additional deployment is necessary as the product automatically detects Oracle WebLogic and allows Oracle WebLogic to read the WAR/EAR files directly.

These utilities will attempt to deploy the Web Applications within the J2EE Web application server as follows:

J2EE Web Application Server	Deployment Details
Oracle WebLogic	Deployed to <code>WEB_CONTEXT_ROOT</code> application set by <code>SPLWEBAPP</code> to server <code>WEB_WLS_SVRNAME</code> by default using <code>WEB_WLSYSUSER</code> and <code>WEB_WLSYSPASS</code> from the <code>ENVIRON.INI</code> as administration credentials.
IBM WebSphere	Deployed to <code>WEB_APP</code> Application on <code>WEB_SVRNAME</code> server by default using <code>WEB_WASUSER</code> and <code>WEB_WASPASS</code> from <code>ENVIRON.INI</code> as administration credentials.
IBM WebSphere ND	Deployed to <code>WEB_APP</code> Application on <code>WEB_SVRNAME</code> server on <code>WEB_NODENAME</code> by default using <code>WEB_WASUSER</code> and <code>WEB_WASPASS</code> from <code>ENVIRON.INI</code> as administration credentials.

The Web Application should be available from the Web Application Server.

5.4 Business Application Server Configuration

It is possible for the Business Application Server logic to be separated from the Web Application Server component. Essentially the product has been split into two distinct EAR files:

- SPLWeb.ear (SPLWEBAPP)** - This contains the Web application server component for the product.
- SPLService.ear (SPLSERVICEAPP)** - This contains the Business Application Server component for the product.

There are two modes of installation:




Figure 25: Installation Modes

- **Local Installation** (also applicable to expanded installations for Development environments) - The Web application server and Business Application are on the same instance of the J2EE Web application server. This is the default behavior of the product for backward compatibility. If this is the mode installed then for configuration the process is a combination of the Web Application Server and Business Application Server configuration and deployment process.

Note: Local installations are recommended for all environments.

- **Decoupled Installation** - The Business Application Server is on a separate instance of the J2EE Web application server. This may be the same machine or different machines. In this case the Web Application Server and Business Application Server are managed and configured separately. To perform a decoupled installation the following must be performed:
 1. The product is installed on the machines housing the Web Application Server and Business Application Server.
 2. A set of servers within one or more instances of the J2EE Web Application Server must be created to house the Web Application Server and Business Application Server separately. This can be on the same machine or across machines.
 3. The Web Application Server and Business Application Server are configured as outlined in Web Application Server Configuration and Business Application Server Configuration.
 4. The WAR/EAR files generated are deployed separately with the SPLWeb.ear (or set by SPLWEBAPP) EAR file deployed to the Web application server as outlined in Web Application Server Deployment Process and SPLService.ear EAR file (or set by SPLSERVICEAPP) deployed to the Business Application Server as outlined in Business Application Server Deployment Process.

Note: For customers using Oracle ExaLogic, Oracle highly recommend that local installations be used for performance reasons.

5.4.1 Business Application Server Concepts

As mentioned previous the Business Application Server component can be deployed within a separate instance of the J2EE Web Application server Software. This effectively allows the Business Application Server to be on separate hardware for architectures where this is a requirement. Typically this separation is implemented for a number of reasons:

- The site has an architectural principle for separating the Business Application Server and Web application server.
- The site prefers to optimize the individual servers for the individual tiers rather than having to compromise when two or more tiers are on the same platform.

The Business Application Server was designed to fit within the same concepts as the Web Application Server. The main differences are:

- Enterprise Java Beans (stateless) are used in the Business Application Server instead of Java Server Pages as used in the Web application server. The name of the EJB is spl-servicebean-<version>.jar (where <version> is the version of the product e.g. 2.0.0).
- Database connectivity is configured in the Business Application Server.

The rest of this section will outline the differences specifically for the Business Application Server.

5.4.2 Business Application Server Configuration Files

Each J2EE Web Application within the J2EE Web application server has its own configuration files. These files are typically embedded within the WAR/EAR files deployed with the product following the J2EE specification (refer the discussion of allowing the externalization of configuration settings for alternative methods). In terms of configuration, the product structure within the WAR/EAR file looks like the following:

Configuration File	Contents
ejb-jar.xml	Enterprise Service Bean configuration
hibernate.properties	Database connectivity
log4j.properties	Logging configuration
spl.properties	Behavior configuration
web.xml	Deployment Descriptor
weblogic.xml	WebLogic extensions
weblogic-ejb-jar.xml	WebLogic extensions for Enterprise Service Bean configuration

5.4.3 Business Application Server Configuration Process

To configure the Business Application Server during the installation process and post-installation then the following process should be used:




Figure 26: Business Application Server Configuration Process

- The `configureEnv` utility is used during installation time and can be used post implementation to set parameters in the `ENVIRON.INI`. If any parameters are derived or set from the `ENVIRON.INI` (see Source column in the relevant section) then the `configureEnv` utility should be used to maintain them.

Note: The `configureEnv` utility should be used to make ANY changes to the `ENVIRON.INI`. Manual changes to this configuration file are not recommended.

- After the `ENVIRON.INI` has been set or altered, the settings must be reflected in the relevant configuration files used by the Business Application Server by running the `initialSetup`:
 - `log4j.properties`
 - `spl.properties`
 - `hibernate.properties`
 - `web.xml`
 - `weblogic.xml`
 - `ejb-jar.xml`
 - `weblogic-ejb-jar.xml`
- The utility uses the templates from the `templates` directory to create substituted copies of these files in a standard location:

Configuration File	Destination
Service Bean	
<u>web.xml</u> <u>Template:</u> web.xml.template	<u>Linux/UNIX:</u> \$SPLBASE/etc/conf/WEB-INF <u>Windows:</u> %SPLBASE%\etc\conf\WEB-INF
<u>spl.properties</u> <u>Template:</u> spl.properties.service.template	<u>Linux/UNIX:</u> \$SPLBASE/etc/conf/service \$SPLBASE/splapp/businessapp/properties <u>Windows:</u> %SPLBASE%\etc\conf\service %SPLBASE%\splapp\businessapp\properties
<u>log4j.properties</u> <u>Template:</u> log4j.properties.service.template	<u>Linux/UNIX:</u> \$SPLBASE/etc/conf/service \$SPLBASE/splapp/businessapp/properties <u>Windows:</u> %SPLBASE%\etc\conf\service %SPLBASE%\splapp\businessapp\properties
<u>hibernate.properties</u> <u>Template:</u> hibernate.properties.web.template	<u>Linux/UNIX:</u> \$SPLBASE/etc/conf/service <u>Windows:</u> %SPLBASE%\etc\conf\service
<u>ejb-jar.xml</u> <u>Template:</u> <u>ejb-jar.xml.template</u>	<u>Linux/UNIX:</u> \$SPLBASE/splapp/businessapp/config/META-INF <u>Windows:</u> %SPLBASE%\splapp\businessapp\config\META-INF
<u>weblogic-ejb-jar.xml</u> <u>Template:</u> <u>weblogic-ejb-jar.xml.template</u>	<u>Linux/UNIX:</u> \$SPLBASE/splapp/businessapp/config/META-INF <u>Windows:</u> %SPLBASE%\splapp\businessapp\config\META-INF

The locations of the configuration files can be summarized in the following figure:




Figure 27: Business Application Server Configuration Files

- At this point you may perform manual changes to the above files to parameters not implemented in the [ENVIRON.INI](#).

Note: Any manual changes are overwritten after running the [initialSetup](#) utility unless the change is reflected in the appropriate template (see [custom templates](#) for more information). Backups should be made of any changes and then manually reapplied to reinstate all manual changes.

- To reflect configuration changes into the product Business EJB Applications the [initialSetup](#) utility, with the `-w` option, must be executed. This will build the necessary `spl-servicebean-<version>.jar` (where `<version>` is the version of the product used) and the `SPLService.ear` EAR file (or name set by `SPLSERVICEAPP`) to be deployed into the J2EE Web application server. This step is optional if configuration overrides are in use (refer the discussion of allowing the externalization of configuration settings for alternative methods).

Depending on the architecture used, the [initialSetup](#) will generate one or more EAR files. At this point the product Business Applications are ready for deployment into the J2EE Web application server.

5.4.4 Quick Reference Guide for Business Application Server Configuration

To make configuration changes to the Business Application Server component of the product uses the following Quick Reference Guide to identify which process should be used:

- If the change is to any setting contained in the ENVIRON.INI for the Business Application Server then you must run the following utilities in the order indicated:
 1. Execute the configureEnv utility to reflect the parameter change in the ENVIRON.INI.
 2. Execute the initialSetup utility (with the -t option) to rebuild the configuration files using the ENVIRON.INI and provided template files. This will reset the configuration to the contents of the base template files or custom template (if used).
 3. Any configuration changes that are overridden by templates (base or custom) must be manually reapplied (if necessary).
 4. Execute the initialSetup utility (with the -w option) to implement the configuration files in the product Business Application files. This step is not necessary of you are using configuration overrides.
- If the change is to any setting not contained in the ENVIRON.INI for the Business Application Server but is in the configuration files for the Business Application Server then you must run the following utilities in the order indicated:
 1. Make any manual changes to the relevant configuration files.
 2. Execute the initialSetup, with the -w option, utility to implement the configuration files in the product Business Application Server files. This step is not necessary of you are using configuration overrides.

5.4.5 Business Application Server Deployment Process

After the configuration of the Business Application Server is complete (as outlined in Business Application Server Configuration Process) the final step to implement the product technically is to deploy the product within the J2EE Web application server.

There are three methods of deploying the product within the J2EE Web application server:

- Use the deployment utilities provided on the console of the J2EE Web application server. The WAR/EAR files that are available under \$SPLEBASE/splapp/applications (or %SPLEBASE%\splapp\applications for Windows) can be manually deployed using the console. Refer to the *Oracle Revenue Management and Billing Installation Guide* for specific platform instructions and the administration guide for the J2EE Web application server.
- Use the deployment utilities provided on the command line of the J2EE Web application server. The WAR/EAR files that are available under \$SPLEBASE/splapp/applications (or %SPLEBASE%\splapp\applications for Windows) can be manually deployed using the J2EE Web application server vendor supplied deployment command line utilities. Refer to the *Oracle Revenue Management and Billing Installation Guide* for specific platform instructions and the administration guide for the J2EE Web application server.
- A number of specific utilities for J2EE Web Application are provided with the product to deploy the EJB Application to the J2EE Web application server. These call the same utilities provided in the previous option but are provided with the product.

This section will outline the latter option.

A number of utilities are provided in the bin directory to deploy the product to the J2EE Web application server. These utilities are outlined below:




Figure 28: Business Application Server Deployment Process

- For the IBM WebSphere/WebSphere ND platform, use the `initialSetup` utility (with the `-d` or `-b` options). This will call the relevant IBM provided utility to deploy the WAR/EAR files into the IBM WebSphere instance.

Note: The `-b` option allows for a decoupled installation on IBM WebSphere. On Oracle WebLogic the console may be used to configure individual elements to achieve the same functionality.

- For Oracle WebLogic, there are two options:
 - Native Mode – Use the WebLogic console or WLST to deploy/redeploy the `EAR` files.
 - Embedded Mode - No additional deployment is necessary as the product automatically detects Oracle WebLogic and allows Oracle WebLogic to read the WAR/EAR files directly.

These utilities will attempt to deploy the EJB Applications within the J2EE Web application server as follows:

J2EE Web Application Server	Deployment Details
Oracle WebLogic	Deployed to <code>WEB_CONTEXT_ROOT</code> application set by <code>SPLSERVICEAPP</code> to server <code>WEB_WLS_SVRNAME</code> by default using <code>WEB_WLSYSUSER</code> and <code>WEB_WLSYSPASS</code> from the <code>ENVIRON.INI</code> as administration credentials.
IBM WebSphere	Deployed to <code>BSN_APP</code> Application on <code>BSN_SVRNAME</code> server by default using <code>WEB_WASUSER</code> and <code>WEB_WASPASS</code> from <code>ENVIRON.INI</code> as administration credentials.
IBM WebSphere ND	Deployed to <code>BSN_APP</code> Application on <code>BSN_SVRNAME</code> server on <code>BSN_NODENAME</code> by default using <code>WEB_WASUSER</code> and <code>WEB_WASPASS</code> from <code>ENVIRON.INI</code> as administration credentials.

5.5 Inbound Web Services Configuration

The Oracle Revenue Management and Billing product supports the ability to implement product Web Services within the J2EE Web Application Server instead of being accessible from the XML Application Integration (XAI) servlet. This has a number of advantages:

- Inbound Web Services can utilize the clustering and high availability features of the J2EE Web Application Server directly.
- Individual Inbound Web Services can be monitored from the J2EE Web Application Server directly. If Oracle Enterprise Manager is used, performance and diagnostic metrics on individual Inbound Web Services can be collected and analyzed for service level tracking and general monitoring.
- Individual Inbound Web Services can be secured using the WS-Policy support available in the J2EE Web Application Server directly. Customer using Oracle WebLogic Server can also utilize the inbuilt [Oracle Web Services Manager](#) within Oracle WebLogic to add access rules to individual Web Services.

Note: It is highly recommended to use Inbound Web Services instead of XML Application Integration as the XAI Servlet will be deprecated in a future release.

5.5.1 Enabling Inbound Web Services

By default, for backward compatibility, the Inbound Web Services feature is disabled. To use the feature it must be enabled and a few features enabled to use the deployment facilities provided by this capability. All these steps must be executed by the relevant administrator user as indicated in the individual steps.

Note: These steps, unless otherwise indicated, are performed once per environment.

5.5.1.1 Enable Inbound Web Services Feature

Note: For customers using the native installation of the product should ensure that the WEB_WLS_SVRNAME is set to the name of the server or cluster used for the environment.

The first step is to enable the feature in the environment configuration file (ENVIRON.INI) to use additional facilities:

- Using the product administrator user on the machines where the product is installed, execute the configureEnv[.sh] –a command after executing the splenviro[n].sh] –e <environmentname> where <environmentname> is the name of the installation environment to enable the feature upon.
- Change the option "Enable Web Services Functionality" on option 50 to true. Save the change using the "P" option.
- Execute the initialSetup[.sh] command to apply the changes to the infrastructure and generate the necessary build files for Inbound Web Services.

5.5.1.2 Set Credentials for Inbound Web Services

Note: Failure to perform this task may cause the deployment of Inbound Web Services to fail.

To deploy the Inbound Web Services seamlessly it is necessary to create an administration credential file so that the build and deployment utilities and online deployment facility for developers can access the domain.

To create this credential file the following commands must be executed:

- Using the product administrator user on the machines where the product is installed, execute the `splenviron[.sh] -e <environmentname>` where `<environmentname>` is the name of the installation environment to enable the feature upon.
- Execute the following command:

UNIX:

```
$JAVA_HOME/bin/java -classpath
$WL_HOME/server/lib/weblogic.jar weblogic.Admin -username
<username> -password <password> STOREUSERCONFIG -
userconfigfile $SPLBASE/etc/.wlsuserconfig -userkeyfile
$SPLBASE/etc/.wlsuserkey
```

Windows:

```
%JAVA_HOME%\bin\java -classpath
%WL_HOME%\server\lib\weblogic.jar weblogic.Admin -username
<username> -password <password> STOREUSERCONFIG -
userconfigfile %SPLBASE%\etc\.wlsuserconfig -userkeyfile
%SPLBASE%\etc\.wlsuserkey
```

Where `<username>` is an Administration password for the domain and `<password>` is the password for that user. For example, these values can correspond to `WEB_WLSYSUSER` and `WEB_WLSYSPASS` (in plain text).

Note: If the password for this user is changed at anytime, this step must be repeated for the facility to continue to operate.

5.5.1.3 Enable USER_LOCK Facility

To prevent multiple parallel deployments, the `USER_LOCK` feature of the database must be enabled on the product user. The following commands must be executed:

- Logon onto the database using SQL Developer or SQL Plus the `SYS` or `SYSTEM` user.
- Execute the following command:

```
@?/rdms/admin/userlock.sql
```

Note: `?` corresponds to `ORACLE_HOME`.

- Grant access to the product user using the following command:

```
grant execute on USER_LOCK to <user>;
```

where <user> is the DBUSER and BATCH_DBUSER¹⁸ from the ENVIRON.INI.

5.5.2 Inbound Web Services Configuration Files

The location of the Inbound Web Service is as follows:




Figure 29: Inbound Web Services Configuration

The following configuration files apply to the Inbound Web Service:

Configuration File	Contents
hibernate.properties	Database connectivity for Inbound Web Services
log4j.properties	Logging configuration
spl.properties	Inbound Web Service specific configurations
weblogic.xml	WebLogic extensions for Inbound Web Services
web.xml.resource	Web application descriptor
webservices.xml.resource	Web service application descriptor

¹⁸ BATCH_DBUSER is used for command line deployment.

5.5.3 Inbound Web Services Concepts

The Inbound Web Services deploys a web archive (WebServices.ear or name set by IWSWAR) containing the components of the inbound Web Services using the following structures:




Figure 30: Inbound Web Services Structures

Structure	Contents
<code>config</code>	Configuration files for Inbound Web Services
<code>gen</code>	Location of files generated by <code>iwsdeploy</code>
<code>lib</code>	Java Libraries
<code>resources</code>	Configuration files, custom policy, XSL and XSD files

The Inbound Web Services was designed to fit within the same concepts as the Web Application Server/Business Application Services. The main differences are:

- The `Weservices.ear` file (or name set by IWSWAR) is located in the `$SPLEBASE/splapp/iws/gen` directory (or `%SPLEBASE%\splapp\iws\gen` on Windows) and is deployed automatically using `iwsdeploy[.sh]` or the online deployment facility.

Note: Customers using native installation can optionally manually deploy the war file, if desired.

- Database connectivity is configured in the Inbound Web Services and included in the build file.

5.5.4 Inbound Web Services Configuration Process

Note:

This section only covers the configuration and deployment of the physical Web Service resources. It does not cover the definition of Inbound Web Services within the product. Refer to the Migrating from XAI to IWS (Doc ID: 1644914.1) available from [My Oracle Support](#) for a discussion of Inbound Web Services.

For this feature to operate, at least one Inbound Web Service should be defined for the build process to execute. If no Inbound Web Services are defined prior to the deployment then the build process will fail.

To configure the Inbound Web Services during the installation process and post-installation then the following process should be used:




Figure 31: Inbound Web Services Configuration Process

- The configureEnv utility is used during installation time and can be used post implementation to set parameters in the [ENVIRON.INI](#). If any parameters are derived or set from the [ENVIRON.INI](#) (see "Source" column in the relevant section) then the configureEnv utility should be used to maintain them.

Note: The configureEnv utility should be used to make ANY changes to the [ENVIRON.INI](#). Manual changes to this configuration file are not recommended.

- After the [ENVIRON.INI](#) has been set or altered, the settings must be reflected in the relevant configuration files used by the Inbound Web Services by running the [initialSetup -t](#):
- The utility uses the templates from the templates directory to create substituted copies of these files in a standard location:

Configuration File	Destination
Service Bean	
<u>spl.properties</u> <u>Template:</u> spl.properties.iws.template	<u>Linux/UNIX:</u> \$SPLEBASE/splapp/iws/config <u>Windows:</u> %SPLEBASE%\splapp\iws\config
<u>log4j.properties</u> <u>Template:</u> log4j.properties.iws.template	<u>Linux/UNIX:</u> \$SPLEBASE/splapp/iws/config <u>Windows:</u> %SPLEBASE%\splapp\iws\config
<u>hibernate.properties</u> <u>Template:</u> hibernate.properties.iws.template	<u>Linux/UNIX:</u> \$SPLEBASE/splapp/iws/config <u>Windows:</u> %SPLEBASE%\splapp\iws\config
<u>web.xml.resource</u> <u>Template:</u> web.xml.resource.iws.template	<u>Linux/UNIX:</u> \$SPLEBASE/splapp/iws/resources <u>Windows:</u> %SPLEBASE%\splapp\iws\resources
<u>webservices.xml.resource</u> <u>Template:</u> webservices.xml.resource.iws.template	<u>Linux/UNIX:</u> \$SPLEBASE/splapp/iws/resources <u>Windows:</u> %SPLEBASE%\splapp\iws\resources
<u>weblogic.xml</u> <u>Template:</u> weblogic.xml.iws.template	<u>Linux/UNIX:</u> \$SPLEBASE/splapp/iws/resources <u>Windows:</u> %SPLEBASE%\splapp\iws\resources

- At this point you may perform manual changes to the above files to parameters not implemented in the [ENVIRON.INI](#).

Note: Any manual changes are overwritten after running the [initialSetup](#) utility unless the change is reflected in the appropriate template (see [custom templates](#) for more information). Backups should be made of any changes and then manually reapplied to reinstate all manual changes.

- To reflect configuration changes into the product the [iwsdeploy](#) utility, must be executed. This will build the necessary Webservices.ear (or the value specified in IWSWAR setting) and to be deployed into the J2EE Web application server. This step is optional if configuration overrides are in use.

Note: For IBM WebSphere customers and customers who want to use manual deployment methods, use the `iwsdeploy[.sh] -b` option to prevent autodeploy.

At this point the product Web Services are ready for deployment into the J2EE Web application server.

5.5.5 Inbound Web Services Deployment Process

After the build of the Inbound Web Services EAR is complete (as outlined in Inbound Web Services Configuration Process) the final step to implement the product technically is to deploy the product within the J2EE Web application server.

There are three methods of deploying the product within the J2EE Web application server:

- Use the deployment utilities provided on the console of the J2EE Web application server. The EAR files are available under \$SPLEBASE/splapp/iws/gen (or %SPLEBASE%\splapp\iws\gen for Windows) can be manually deployed using the console. Refer to the Installation Guide for specific platform instructions and the administration guide for the J2EE Web application server.
- Use the deployment utilities provided on the command line of the J2EE Web application server. The EAR files are available under \$SPLEBASE/splapp/iws/gen (or %SPLEBASE%\splapp\iws\gen for Windows) can be manually deployed using the J2EE Web application server vendor supplied deployment command line utilities. Refer to the Installation Guide for specific platform instructions and the administration guide for the J2EE Web application server.
- Use the iwsdeploy utility for command line access for deployment.

Note: IBM WebSphere customers should not use the deployment options in this command. Use the -b options to build but not deploy. Manual deployment is recommended.

- Use the Inbound Web Services online transaction

A number of utilities are provided in the bin directory to deploy the product to the J2EE Web application server. These utilities are outlined below:




Figure 32: Inbound Web Services Deployment Process

These utilities will attempt to deploy the Web Services within the J2EE Web application server as follows:

J2EE Web Application Server	Deployment Details
Oracle WebLogic	Deployed application set by IWSWAR to server WEB_WLS_SVRNAME by default using WEB_WLSYSUSER and WEB_WLSYSPASS from the ENVIRON.INI as administration credentials.
IBM WebSphere	Deployed to IWSWAR Application on WEB_SVRNAME server by default using WEB_WASUSER and WEB_WASPASS from ENVIRON.INI as administration credentials.
IBM WebSphere ND	Deployed to IWSWAR Application on WEB_SVRNAME server on WEB_NODENAME by default using WEB_WASUSER and WEB_WASPASS from ENVIRON.INI as administration credentials.

5.5.6 Quick Reference Guide for Inbound Web Services Configuration

To make configuration changes to the IWS component of the product uses the following Quick Reference Guide to identify which process should be used:


- If the change is to any setting contained in the [ENVIRON.INI](#) for the IWS then you must run the following utilities in the order indicated:
 1. Execute the `configureEnv` utility to reflect the parameter change in the [ENVIRON.INI](#).
 2. Execute the [initialSetup](#) utility (with the `-t` option) to rebuild the configuration files using the [ENVIRON.INI](#) and provided template files. This will reset the configuration to the contents of the base template files or [custom template](#) (if used).
 3. Any configuration changes that are overridden by templates (base or [custom template](#)) must be manually reapplied (if necessary).
 4. Execute the [initialSetup](#) utility (with the `-w` option) to implement the configuration files in the product IWS files. This step is not necessary if you are using configuration overrides.
 5. Execute the [iwsdeploy](#) utility to build and deploy.
- If the change is to any setting not contained in the [ENVIRON.INI](#) for the IWS but is in the configuration files for the IWS then you must run the following utilities in the order indicated:
 1. Make any manual changes to the relevant configuration files.
 2. Execute the [initialSetup](#), with the `-w` option, utility to implement the configuration files in the product IWS files.

5.5.7 Inbound Web Services Deployment Utilities

After the configuration of the Inbound Web Services is complete (as outlined in Inbound Web Services Configuration Process) the final step to implement the product technically is to deploy the product within the J2EE Web application server.

There are three methods of deploying the Inbound Web Services component within the J2EE Web application server:

- An Inbound Web Services Deployment facility available from the product online. This is accessible from the Admin → I → Inbound Web Services Deployment menu item. This is suitable for development environments only. For example:



The screenshot shows the 'Inbound Web Service Deployment' interface. At the top, there are 'Bookmark' and 'Refresh' buttons. Below that, a 'Main' tab is selected, showing 'Deploy Inbound Web Services'. A message indicates the 'Last Deployment' was on 03-23-2015 10:44PM with 4 services deployed and 0 failures. A large red box highlights the 'Deploy' button. Below this, the 'Deployment Status' section lists four services with their details:

Web Service Name	Description	Service Revision	Deployment Status	Trace	Debug	Active
1 F1-EmailService	Real-time Email Service	2	Deployed	N	N	Y
2 F1-ORAGEOCD	Geocode Address XAI Inbound Service	3	Deployed	N	N	Y
3 F1-SmsReceive	Receive SMS Message XAI Service	3	Deployed	N	N	Y
4 F1-UpdateAndTransitionSyncRequest	F1-UpdateSyncRequest	3	Deployed	N	N	Y

Figure 33: Inbound Web Services Online Transaction

- Use the iwsdeploy utility to trigger a deployment from the command line.
- Execute the iwsdeploy utility but manually deploy the Web Services EAR file to the server(s) or cluster using the J2EE console or deployment utilities.

5.6 Batch Server Configuration BATCH

The batch component contains a number of configuration files and utilities to manage the configuration of the cluster, threadpools and submitters. This section outlines the configuration files and configuration process for configuring batch.

5.6.1 Batch Configuration Files

As with the online component of the Oracle Utilities Application Framework there are a number of configuration files that control the performance and behaviour of the batch component.

The batch component houses the configuration files differently to the online and web services component. The online and web services are housed within a J2EE Web Application Server and therefore the configuration files are located according to the J2EE standards.

In the batch component the configuration are housed in directories as the batch component is housed as a standalone process that is clustered using Oracle Coherence. Therefore, during the configuration process, the configuration files used by the batch component are built using templates using the `initialSetup` utility. This utility deposits the configuration files in the `$SPLDBASE\splapp\standalone\config` directory (or `%SPLDBASE%\splapp\standalone\config` directory in Windows).

The figure below summarizes the directory structure and the relevant configuration files:




Figure 34: Batch Configuration Files

The following configuration files (along with their templates) are listed below:

Configuration File	Contents
e0Batch.properties	General environment settings
hibernate.properties	Database connectivity
log4j.properties	Logging settings
spl.properties	Application behaviour
submitbatch.properties	submitjob default settings
submitbatchlog4j.properties	submitjob logging settings
threadpoolworker.properties	threadpoolworker configuration
tpwlog4j.properties	threadpoolworker logging settings
coherence-cache-config.xml - Oracle Coherence Configuration BATCH	Cache settings for cluster
tangasol-coherence-override.xml	Override setting for cluster

5.6.2 General Configuration Process

To configure the batch component during the installation process and post-installation then the following process should be used:




Figure 35: Batch Configuration Process

- The `configureEnv` utility is used during installation time and can be used post installation to set parameters in the `ENVIRON.INI`.

Note: The `configureEnv` utility should be used to make any changes to the `ENVIRON.INI`. Manual changes to this configuration file are not recommended.

- After the `ENVIRON.INI` has been set or altered, the settings must be reflected in the relevant configuration files used by the batch component using the `initialSetup` utility. The `initialSetup` utility takes the relevant templates, builds the configuration files and deposits them in the `$SPLEBASE\splapp\standalone\config` directory (or `%SPLEBASE%\splapp\standalone\config` directory in Windows).

The configuration files are now ready to be used for the batch component. Additional configuration can be performed using `bedit`.

5.6.3 Configuring Batch Using bedit

The [bedit](#) utility is a set of wizards that allow a batch configuration to be built for an implementation using simple commands. The utility uses a set of templates to build a complete set of configuration files for the cluster, its threadpools and submitters at a global and individual level.

For guidelines and scenarios using this facility, refer to the Batch Best Practices (Doc ID: 836362.1) whitepaper available from [My Oracle Support](#).

5.6.3.1 Batch Configuration Overview Using edit

The bedit utility allows for a set of configuration files to be built on top of the global configuration setting managed using the Batch Configuration process. The following process should be used:

- **Global Settings** - Specify global batch settings using the `configureEnv` utility to set the defaults in the `ENVIRON.INI`.
- **Apply Settings** - Apply any configuration settings to the global templates and default configuration files using the `initialSetup`¹⁹ utility.
- **Perform Cluster Configuration** - Configure the desired cluster configuration using bedit. Clusters are setup once, per environment either using multicast, unicast or single server optimized configurations.
- **Perform Threadpoolworker Configuration** - Configure the desired threadpoolworker configuration using bedit. Threadpoolworkers can be created on an individual basis with unique configurations or labelled to share configurations.
- **Perform Submitter Configuration** - Configure the desired submitter configuration using bedit. Submitters can be setup for specific development execution modes (THIN or LOCAL), generic configuration or project specific jobs.

The process is shown below:




Figure 36: bedit Configuration Process

¹⁹ Use the `-t` option to allow templates to be rebuilt only. Using other options may affect online.

Note: At any time the file name and location of the generated file is determined at the start of the edit session or using the `what` command.

5.6.3.2 Batch Edit Usage Guidelines

The `bedit` utility is available to simplify the creation and maintenance of these files to promote stability and flexibility whilst minimizing maintenance mistakes. The following guidelines apply when using the utility:

- The command line options specify the configuration file to be modified. The specific configuration file or the `shortcut` option can be used to set the scope of the command.
- Pre-optimized specialist templates (with `.be` extension) are used to decide the parameters applicable to the setting or command used in the configuration file being edited. The template name is displayed at the start of execution to confirm the configuration file edited.
- Configuration settings can be added, modified or deleted using interactive commands. The following commands are supported:

Command	Usage
<code>add <group></code>	Add a group <code><group></code> with all its sub-elements. Values for the variables are defaulted from the template.
<code>del <group></code>	Delete the group <code><group></code> and all its sub-elements.
<code>exit</code>	Exit the editor. If changes have been made, confirmation may be required.
<code>help <topic></code>	Show online help for command or setting. Without a topic a list of topics for the configuration file and commands are listed
<code>save</code>	Save any changes to the configuration file
<code>set <var> <value></code>	This command to update a variable's <code><var></code> to value <code><value></code> . If there are multiple sub-elements for a group, the variable name must be fully qualified by its parent group(s) - e.g. <code>set pool.2 poolname DEFAULT</code> . If there is only one group, the variable does not need to be qualified - e.g. <code>set poolname DEFAULT</code> .
<code>what</code>	This command shows which file is being edited and the template on which it is based.

- The templates will generate the necessary settings based upon the scope of the command. Use the online help to determine valid settings for your configuration.
- User preferences for labels and cluster types are stored in the `be.prefs` file.
- Using the `save` command will reflect your changes to the configuration file directly.
- If `exit` command is issued and changes have been detected then a confirmation message will be issued. Press `y` to save, `n` to quit without saving or `c` to cancel out of `exit` command.

Each subsection will outline specific settings within the scope of each configuration.

5.6.3.3 Cluster Configuration Using bedit

Oracle Coherence is used to define and manage the batch cluster. The cluster must be configured to decide how the cluster will operate on the network and the scope of the cluster. The major decision for this step in the process is the type of cluster to implement. There are three styles of cluster supported:

- **Multicast cluster** (default) - A batch cluster based upon the multicast network protocol. The protocol requires a multicast address and common port. This protocol supports dynamic clustering.
- **Unicast cluster** - A batch cluster based upon unicast network protocol. Each host and port in the cluster must be explicitly configured.
- **Single Server cluster** - A batch cluster confined to a single server using unicast. This is designed for use in non-production environments to simplify the configuration.

The templates for these cluster types are as follows:

Template	Usage
tangosol-coherence-override.mc.be	Multicast cluster
tangosol-coherence-override.ss.be	Single Server cluster (useful for non-production environments)
tangosol-coherence-override.wka.be	Unicast (or wka) cluster

To configure the cluster use one of the example commands:

Commands	Description
bedit.sh -c -t <type>	Create or edit Cluster configuration. The -t option is used to set the cluster type as specified (mc - Multicast, wka - Unicast or ss - Single Server). Specifying the -t option on an already defined cluster may change the type.
bedit.sh -c	Maintain the cluster configuration. Cluster type is defaulted from be.prefs.
bedit.sh tangosol-coherence-override.xml	Edit the tangosol-coherence-override.xml file.

Once the configuration is opened the following settings need to be configured:

Variable	ss	wka	mc	Recommendations
cluster	■	■	■	Unique cluster name for environment. This must be unique for the cluster. Typically use the environment name or database name.
address	■	■	■	IP address or host name for this node in the cluster. Use localhost if possible to minimize maintenance across hosts.

Variable	ss	wka	mc	Recommendations
port	■	■	■	Unique port used for cluster. This must be unique per cluster per host. Its use will vary from cluster type to cluster type. Refer to the online help for more information.
loglevel	■	■	■	The logging level associated with cluster operations. Refer to the online help to decide the amount of information you wish to log. The higher the value the more that is logged. High values are used by developers typically.
mode	■	■	■	The Coherence mode that the cluster is to be scoped to. Refer to the online help for more information.
socket		■		This is a section for each of the hosts in the Well Known Address format. Each host is a separate socket entry. Refer to the online help for more information.
wkaaddress		■		The IP address or host name of the member of the cluster assigned to this socket.
wkaport		■		The port number assigned of the member of the cluster assigned to this socket. This value ideally is the same across all hosts in the cluster but can be overridden to overcome port conflicts. The port number on each node must match the number assigned to the port value.

For unicast implementations a socket section must be created per host/port combination defined in the file using the following commands:

- Use the add socket command to add a new socket group. The group name generated will be in the form socket.<number> where <number> is the sequence number. For example:

```
> add socket
...
socket.2
wkaaddress (localhost)
wkaport (42020)
```

- Set the wkaaddress and wkaport using the set socket.<number> <variable> <value> where <number> is the sequence number, <variable> is wkaaddress or wkaport and <value> is the desired value. For example:

```
> set socket.2 wkaport 6402
...
socket.2
wkaaddress (localhost)
wkaport (6402)
```

- Repeat for each node in the cluster.

5.6.3.4 Threadpoolworker Configuration Using bedit

Once a cluster is defined the threadpools that will execute across that cluster must be defined with their name and attributes. The product supports different types of threadpools that can execute batch processes with the following:

- **Cache Threadpools** - Threadpoolworkers that do not execute jobs but act as co-ordination node for network traffic. It is recommended that there be at least one cache threadpool per physical host per cluster. For a discussion of cache threadpools, refer to the [Batch Best Practices](#) (Doc ID: [836362.1](#)) whitepaper available from [My Oracle Support](#). This threadpool type has [tangosol.coherence.distributed.localstorage](#) set to true
- **Job Threadpools** - Threadpoolworkers that are optimized to run batch threads with support for additional java options and other cluster specific optimization settings.
- **Default Threadpools** - For backward compatibility, the default template used is pre-optimized with settings from past releases. It is recommended to migrate from this template to job template.

The templates for these threadpool types are as follows:

Template	Usage
threadpoolworker.be.template	Default template
threadpoolworker.cache.be.template	Cache Threadpool template
threadpoolworker.job.be.template	Job Threadpool templates

To configure the cluster use one of the example commands:

Commands	Description
bedit.sh -w -l <type>	Create or edit threadpool configuration. The -l option is used to set the label type as specified (cache - cache or job - Job).
bedit.sh -w	Maintain the default threadpool configuration.
bedit.sh threadpoolworker.properties	Edit the <code>threadpoolworker.properties</code> file.

Once the configuration is opened the following settings need to be configured:

Parameter	Recommendations
minheap	Minimum JVM Heap size
maxheap	Maximum JVM Heap size
maxperm	Maximum JVM permgen size
daemon	Whether the threadpool should run the online submission daemon. This value should be set to false for production environments.

Parameter	Recommendations
dkidisabled	Key insert behavior
storage	Whether local storage is enabled. Used for cache threadpools.
distthds	Number of internal threads used for cache threadpools.
invocthds	Number of internal threads used for invocation services.
role	Information role for the threadpools used for monitoring
jmxstartport	JMX Start Port
pool	Group section for each threadpool
poolname	Name of threadpool
threads	Maximum number of threads for the threadpool per instance

For multiple threadpools per configuration use the following process:

- Use the `add pool` command to add a new pool group. The group name generated will be in the form `pool.<number>` where `<number>` is the sequence number. For example:


```
> add pool
...
pool.2
wkaaddress (localhost)
wkaport (42020)
```
- Set the `poolname` and `threads` using the `set pool.<number> <variable> <value>` where `<number>` is the sequence number, `<variable>` is `poolname` or `threads` and `<value>` is the desired value.

5.6.3.5 Submitter Configuration Using bedit

The last step in configuration is to configure the submitters. A submitter is a JVM that submits jobs or threads of jobs to a threadpoolworker and waits for the thread to complete. It is responsible for interfacing to the threadpoolworker and also provides an interface to the process that submits the jobs in the first place (e.g. a third party batch scheduler or Oracle Scheduler).

A submitter needs one or more of the following pieces of information:

- It needs a configuration file that defines the parameters to be used for the individual batch process being executed. These can be global configuration files or individual configuration files optimized for a particular batch process.
- Command line options to set or override particular configuration parameters that define the execution parameters for the individual process or thread.

The single execution of a submitter can run a single threaded batch job, a single individual thread of a multi-threaded batch job or all threads of a multi-threaded job.

To create a specific configuration file for a batch job any of the following commands can be used:

Commands	Description
bedit.sh -l <type>	Create or edit submitter configuration. The -l option is used to set the label type for development purposes as specified (THIN - THIN mode or LOCAL - local mode).
bedit.sh -b <batch_cd>	Create or edit submitter configuration for job <batch_cd>.
bedit.sh -s	Edit default submitter configuration

Once the configuration is opened the following settings need to be configured:

Parameter	Recommendations
poolname	Name of threadpool to execute this submitter within
threads	Thread limit of submitter. The number of threads must be equal to or less than the number of threads allocated to executing instances of the threadpool
commit	Default commit interval. This overrides the commit interval defined internally for the batch job.
user	The User ID, defined to the User record, to be used to determine execution permissions and is used for records updated and created by this process. This MUST be a valid defined user.
lang	The language pack used for the batch process (default is ENG)
storage	This sets whether this node is a storage node. Used for submitters that use THIN mode (for developers). This value is recommended to be set to false for all other submitter types.
role	The role used for this submitter. This is used for the JMX monitoring interface as a filter. By default the batch code used for this value.
soft	Group section for soft parameters. One section per parameter
parm	Parameter name as outlined on Batch Control.
value	Value assigned to the parameter

For multiple parameters per configuration use the following process:

- Use the `add soft` command to add a new parameter group. The group name generated will be in the form `soft.<number>` where `<number>` is the sequence number. For example:

```
> add soft
...
soft.2
  parm (maxErrors)
  value (500)
```

- Set the `parm` and `value` using the `set pool.<number> <variable> <value>` where `<number>` is the sequence number, `<variable>` is `parm` or `value` and `<value>` is the desired value. For example:

```
> set soft.2 parm fred
...
soft.2
  parm (fred)
  value (500)
```

5.6.4 Batch Configuration Guidelines

The following sections outline general guidelines for batch configuration.

5.6.4.1 Cache Threadpools

One of the new facilities in the batch architecture is the ability to define cache or storage nodes in your architecture. By default a batch cluster communicates across the cluster elements such as threadpools the state of other elements in the cluster. While this has benefits, as any element in the cluster can be queried, via JMX, to find out the global status of all active processes in that cluster, it can generate a large amount of network traffic and cause instability as the cluster is performing a large amount of maintenance operations. To address this it is now possible in the product to create cache or storage threadpools. These act as conduits with the architecture and greatly reduce the network traffic and overheads in managing the cluster. This translates to more stable clusters.

The communications between elements are shown below:




Figure 37: Cache Architecture

The performance advantages of the cache increases with the number of elements the cluster has to manage and cache threadpools have the following implementation recommendations:

- Cache threadpools do not execute any threads of any jobs within them. They are exclusively used for administration, a storage node for the cluster state and a conduit for cluster management.
- Cache threadpools act as Coherence local storage nodes to maintain the integrity of the cluster and allow cluster management.
- Cache threadpools are ideally suited to allow JMX connections to monitor the performance of the cluster using the [Batch JMX interface](#).
- At least one cache threadpool per cluster per host is recommended. Multiple cache threadpools can be implemented where high availability is required or there are large number of submitters, threads and/or threadpools to manage.
- If a cache threadpool is shut down and no cache threadpools are active at any time, the cluster will not revert to individual elements communicating across other elements.
- To create cache clusters, use the [bedit\[.sh\]](#) -l cache command. A prebuilt template is created for the cache where `storage` is enabled, `distthds`, `invocthds` and the number of threads is set to 0 (to prevent jobs from actually running in the cache).

5.6.4.2 Adding Custom JMX Information to Jobs

The [Batch Server JMX interface](#) can be extended for additional tags using a new parameter `f1.jmxInfo` for filtering purposes or additional documentation. For example:

ExecutionStrategyClass	com.splwg.base.api.batch.SingleTransactionStrategy
JMXInfo	foo2=bar2 foo1=bar1
LanguageCd	ENG
More Execution Attributes	

Figure 38: JMX Info in jconsole

The submitbatch.properties file for the particular job should have the following additional parameter:

com.splwg.batch.submitter.softParameter.f1.jmxInfo.<tag>=<value>

where:

Command Line Option	Description
<tag>	Additional JMX information identifier
<value>	Value for parameter

Multiple parameters of this type are supported within a single configuration file.

For example:

com.splwg.batch.submitter.softParameter.f1.jmxInfo.foo=bar

When using bedit the command sequence to use this facility is:

- Add a soft parameter section for each desired tag/value pair using the command (a section soft.<sequence> is created where <sequence> is a generated sequence number):

add soft

- Specify the parm property as f1.jmxInfo.<tag> where <tag> is the desired tag using the command:

set soft.<sequence> parm f1.jmxInfo.<tag>

- Specify the value property as the desired value for the tag using the command:

set soft.<sequence> value <value>

It is possible to specify this setting on the [submitjob\[.sh\]](#) command using the -x option. For example:

submit.sh ... -x f1.jmxInfo.foo=bar

5.7 Oracle Cloud Support

The Oracle Utilities products are progressively being implemented on Oracle Cloud in both Software as a Service (SaaS) and Platform as a Service (PaaS). This has resulted in new cloud based configurations and features. These features are also available for customers with on-premise and hybrid implementations. This section will outline the additional configuration facilities that can be used for on-premise implementations.

5.7.1 Support for Host Whitelisting

The hosts and port numbers used by the feature sets in the product are typically restricted in scope for on-premise products but on the cloud, the ports and hosts can be restricted to ensure compliance. The product supports the configuration of the hosts and ports, that are accessible from the online system, can be specified in a whitelist which is validated at configuration time and runtime.

There are a number of configuration settings that are control the whitelist:

- **[CLOUD_RESTRICTION_URLS_ENABLE](#)** - Whether the whitelisting feature is used or not (default is false).
- **[CLOUD_WHITE_LIST_PATH](#)** - The full path to the whitelist file for Oracle Cloud. This variable should not be populated for on-premise implementations. This is only used if CLOUD_RESTRICTION_URLS_ENABLE is set to true.
- **[CLOUD_CUSTOM_WHITE_LIST_PATH](#)** - The full path to a custom whitelist for Oracle Cloud or on-premise implementations. This is only used if CLOUD_RESTRICTION_URLS_ENABLE is set to true.

The format of the whitelist is an XML format document:

Attribute	Description
<whitelist>	Root node for whitelist XML
<host>	A section for the host
<name>	Host name or IP Address for host. Wildcards are supported. IPV4 and IPV6 formats are supported.
<port>	Port Number. Wildcards are supported.
<protocol>	Protocol supported (HTTP or HTTPS support). Wildcards are supported.

For example:

```
<?xml version="1.0" encoding="UTF-8"?>
<whitelist>
  <host>
    <name>myhost.example.com</name>
    <port>10201</port>
    <protocol>HTTPS</protocol>
  </host>
  <host>
    <name>myhost2.example.com</name>
    <port>6501</port>
    <protocol>HTTPS</protocol>
  </host>
  <host>
```

```

<name>myhost.example.com</name>
<port>10200</port>
<protocol>HTTP</protocol>
</host>
<host>
  <name>*.company.com</name>
  <port>*</port>
  <protocol>*</protocol>
</host>
</whitelist>

```

There must be a separate entry for each host, name, port and protocol combination.

The following components are validated and when:

Component	Design Time Validation	Run Time Validation
Message Sender Context	■	
JNDI Server	■	
XAI JDBC Connection	■	
Web Service Adapter	■	■
Feature Configuration	■	
Reporting Options	■	
External Navigation Keys	■	■
XAI Executer	■	
XAI Command	■	
HTTP Sender		■
Real Time HTTP Sender		■
JSON Sender		■
Real Time Email Sender		■
JMS Sender		■
SMS BPEL Sender		■
Web Services (WSDL, OPA etc)		■

5.7.2 Domain Template Support

Note:

This feature only applies to Oracle WebLogic 12 and above implementations only.

Before using Domain Templates refer to the [Fusion Middleware Creating Domain Templates Using the Domain Template Builder](#) for more information about Domain Templates and Extension Templates.

Oracle WebLogic supports the concept of [Domain Templates](#). These are predefined domain configurations that can be used to establish the domain configuration reducing the need for manual effort in building domains.

The product now ships with a number of base templates that can be used when creating the domain:

- **Oracle-Utilities-Simple-Linux-<version>.jar** - This is a template useful for non-production installations with an Administration server and single product server with the base domain attributes, as per the native installation.
- **Oracle-Utilities-Complex-Linux-<version>.jar** - This is a template useful for clustered production installations with an Administration server and single product cluster (with a single server) with the base domain attributes, as per the native installation.

These templates are located in `$SPLBASE/tools/domaintemplates`. These can be used with the [Oracle WebLogic Configuration Wizard](#) or Oracle WebLogic installer.

If a native mode installation is desired, it is recommended to use the domain templates as provided to reduce the amount of manual configuration.

Oracle WebLogic ships with a [Template Builder](#) to allow implementations to build their own custom templates. If the domain has been customized for any reason, then using a custom domain template can simplify the provisioning of new domains.

When using the domain template builder ensure the following is included in your custom domain template:

- Ensure the servers allocated to the product are included.
- Ensure all the deployments allocated to the product are included.
- Ensure the secure domain configuration is included. Optionally users can also be included. At a minimum the administration users should be transferred, if desired.
- Ensure the XML registry is included.
- Ensure JDBC and JMS resources used by the product are also included.

5.7.3 Diagnostics Support (WLDF)

Note:

This feature only applies to Oracle WebLogic 12 and above implementations only.

Refer to [Configuring and Capturing Diagnostic Images](#) for additional advice.

Oracle WebLogic includes a diagnostics capability in the form of Oracle WebLogic Diagnostics Framework (WLDF). Typically most diagnostics tools only detect an issue after it has happened, which means important diagnostic information may not be captured. The WLDF captures information at the time of the issue and after to provide additional diagnostics in a standard format for inclusion in diagnostic tools built into Oracle products and for Service Requests within My Oracle Support.

The diagnostic engines works in the following way:

- The diagnostics facility is enabled to capture information. As part of that enablement the location of the diagnostics is configured.
- A set of rules are added to configure the diagnostics engine to recognize issues that are above and beyond the typical issues. WLDF detects common java issues automatically.
- When a rule or the diagnostic engine detects an error is occurring or has occurred, it gathers as much diagnostics information it can at the time of the error and creates a diagnostic image which assembles the diagnostics information into a structured format. This is placed in the configured location.
- Diagnostic images are available from the console as well as Oracle Enterprise Manager where they can be viewed, analyzed and attached to Service Requests as necessary.

The product now supports the WLDF using the following:

- A set of configuration settings that enable the support as well as set some basic settings. These settings are primarily used for embedded installations. For native installations, the WLDF definitions are included in the provided [Domain Tempates](#).

Note:

For customers with preexisting native installations wanting to use this facility, it is recommended to enable the facility in an embedded installation and manually make the changes to your domain to match the settings using the Oracle WebLogic console or Oracle Fusion Middleware console.

- A set of base rules to instruct WLDF the conditions to track and detect issues. These are customizable rules for Oracle WebLogic to detect any issues outside of typical issues.

The following parameters control the implementation of the Diagnostics Framework:

- [WLS DIAGNOSTIC CONTEXT ENABLED](#) - This enables (true) or disables (false) the diagnostics generation support in the product.
- [WLS DIAGNOSTIC BUILT IN MODULE](#) - If WLS_DIAGNOSTIC_CONTEXT_ENABLED is enabled, this sets the name of the diagnostics module to be used for diagnostics. The default value is None.
- [WLS DIAGNOSTIC VOLUME](#) - If WLS_DIAGNOSTIC_CONTEXT_ENABLED is enabled, this determines the volume of diagnostics generated for the diagnostic tools such as [Flight Recorder](#). The default is Off.

For native installations, the following process should be used from the Oracle WebLogic console to enable support:

1. Navigate to the Environment → Servers menu item and click on the product server name to enable.
2. In the Configuration tab, change the value of Diagnostic Volume to the desired level of diagnostics. It is recommended to use Low as a minimum. Save the changes and repeat for each product server (if multiple are implemented in the domain).
3. Navigate to the Diagnostics → Built-in Diagnostics Modules menu item and select the product servers. Click on the Activate button to enable basic diagnostics. This should change the Status to Active.
4. If a custom Diagnostic Module is to be used, then navigate to the Diagnostics → Diagnostic Modules menu item and select the desired diagnostic module to maintain. From the Targets tab, select the product servers to apply the desired diagnostics module. Save the changes.

5.7.4 ECID Support

Note:

This feature only applies to Oracle WebLogic 12 and above implementations only.

Any settings outlined here are for embedded implementations only. Additional steps for native installations are also outlined.

Oracle WebLogic includes a set of facilities to add additional information to transactions known as the Execution Context Identifier (ECID). The single ECID is attached to each unique transaction within the product. This allows diagnostic tools to perform forensic analysis based on the identifier across the architecture.

There are a set of rules that apply to the ECID within the product:

- A unique ECID is generated at the start of a transaction within the product. This ECID is active for all calls within the product till a **COMMIT** or **ROLLBACK** is issued by the product. This constitutes a transaction boundary within the product.
- The ECID is only generated for online web based transactions in the present release.
- The ECID is used within the logs, diagnostic images and transaction tracking facilities within Oracle WebLogic and the related database connections.
- The use of ECID is optional and disabled, by default, for backward compatibility.
- The ECID is used by the various Oracle diagnostics tools such as [Oracle Enterprise Manager](#), [JVMD](#) and [Business Transaction Management](#).

The following parameters control the implementation of the Diagnostics Framework:

- **WLS_DIAGNOSTIC_CONTEXT_ENABLED** - This enables (true) or disables (false) the diagnostics generation support in the product.

For native installations, the following process should be used from the Oracle WebLogic console to enable support:

- Navigate to the Diagnostics → Context menu item.
- Select the product servers and click on Enable to enable ECID support.
- The status of the selected servers should change to Enabled.

5.7.5 Global Cache Flush Support

Note:

This facility is only available in Oracle WebLogic.

One of the architectural features of the products is the support for caching of commonly used data. This cache is used to prevent the transactions to perform unnecessary calls for commonly used data. This cache is loaded and maintained by the product automatically.

In some cases, it may be necessary to force a refresh of the cache to reload the static data. Whilst a number of utilities are provided to [flush the online/web services](#) cache as well as the [batch cache](#), if there were a number of servers or threadpools then the cache request may have to be performed on each threadpool or server.

In the current release any cache request can be configured to flush all caches, known as a global flush, across the architecture. Use of this facility is optional, but recommended in production environments to ensure consistent processing.

To use this facility the following must be configured:

- The ouaf.flush.jms.disabled property in the spl.properties file must be set to false.
- The ouaf.flush.jms.connection, ouaf.flush.jms.requestTopic and ouaf.flush.jms.responseTopic properties must be populated in the spl.properties with the JMS resources used. These JMS resources must be created within the domain of the product.

Once enabled all flush requests now are global.

The global flush operates in the following way:

- When a flush is requested from the online using the JSP or JMX facility, Web Services via JMX and batch via running F1-FLUSH, an entry is placed in the JMS Topic dictated by ouaf.flush.jms.requestTopic.
- Each of the components of the architecture has subscribed to the JMS resource specified by ouaf.flush.jms.requestTopic at their startup time.
- When they receive a message in that topic, each component flushes their cache according to their local methods and sends an appropriate response in the JMS resource specified by ouaf.flush.jms.responseTopic indicating success or failure. This JMS resource may be monitored using the Oracle WebLogic console, Oracle Enterprise Manager, a JMS Browser or the JMS Viewing facility within the product.

Note:

It is possible to configure additional features of the JMS resources outlined above to decide on retention periods and other settings. Refer to the [Understanding Oracle WebLogic JMS documentation](#) for additional features.

5.7.6 Java Flight Recorder Support

Note:

This feature only applies to Oracle JDK 7u60 and above implementations only.

If Java Flight Recorder is enabled then these will also be included in Diagnostic Images if Diagnostics is enabled.

The [Java Flight Recorder](#) is a component of Java that collects diagnostic and profile data for a running Java Virtual Machine (JVM). The product now supports the enabling of the Java Flight Recorder for tracking online java performance.

To enable the support for Java Flight Recorder in a native installation the following process must be performed on the Oracle WebLogic console:

- Navigate to the **Environment** → **Servers** menu item. Click on the product server to enable configuration.
- Navigate to the Server Start tab on the Configuration tab and add the following java options to the Arguments field:
-XX:+UnlockCommercialFeatures -XX:+FlightRecorder

Note:

If your site is using the setUserOverrides.sh facility, place these arguments in that script as an alternative.

- Navigate to the General tab on the Configuration tab and alter the Diagnostics Volume to the desired amount of diagnostics to capture. At a minimum this value should be set to Low.
- Optionally, enable [ECID tracking](#) for advanced diagnostics for tracing individual transactions.
- Edit any Diagnostic Modules you are using, or create one if you are not using a module and configure a DyelInjection Monitor as outlined in [Configuring the DyelInjection Monitor to Manage Diagnostic Contexts](#). Filters may be specific to focus the scope of the monitor if desired.

5.7.7 Work Manager Support

Note:

This feature only applies to native installation implementations only.

This feature is only available in Oracle WebLogic implementations only.

Oracle WebLogic supports [Work Managers](#) that allow implementations to set limits on the server to help optimize performance and prevent server overloading. The product now allows specification of Work Managers to provide additional throttling capabilities.

To use this feature the following must be performed within the Oracle WebLogic console:

- Create a Work Manager with an appropriate name using the Environment → Work Managers menu item. Target the Work Manager to the product servers using the Targets tab. By default, the Work Manager will be unlimited and have no restrictions.
- The product supports the following [constraints](#):
 - Minimum Threads Constraint
 - Maximum Threads Constraint
 - Capacity Constraint
- It is also possible to override the action used for Stuck Threads.
- Request Class is currently not supported.
- Save the changes.

Work Managers can be monitored using Oracle WebLogic console or Oracle Enterprise Manager. Refer to the [Work Managers](#) documentation for additional information.

5.7.8 Trust Store Support

Note: For more information about trust stores refer to the [JSSE documentation](#) and [Keystore Configuration \(Doc ID: 2014161.1\)](#).

The product now supports trust stores as well as key stores for two phase authentication for the online web channel. The format of a trust store is the same as the keystore but the trust store is used to verify credentials whilst the keystore provides the credentials.

The following in the **ENVIRON.INI** entries need to be provided:

- TS_ALIAS
- TS_ALIAS_KEYALG
- TS_ALIAS_KEYSIZE
- TS_HMAC_ALIAS
- TS_HMAC_ALIAS_KEYALG
- TS_HMAC_ALIAS_KEYSIZE
- TS_IMPORT_KEYSTORE_FOLDER
- TS_KEYSTORE_FILE
- TS_MODE
- TS_PADDING
- TS_STOREPASS_FILE
- TS_STORETYPE

6. Miscellaneous Operations and Configurations

6.1 Enabling Email Logging from Log4j

The following sample configuration will enable email logging of ERROR level log messages in the product. When an error is encountered in startup and during operations of the product any ERROR message displayed on the console log file will be emailed to an Administrator's email account or email group.

Note: This change outlined below will make manual changes to a configuration file. Execution of `initialSetup` may overwrite these changes unless template overrides are used. Please ensure you make adequate backups to preserve this change. Refer to <http://logging.apache.org/log4j/1.2/apidocs/org/apache/log4j/net/SMTPAppender.html> for details of the appender.

The following changes are required to enable this,

1. Open the `log4j.properties` in the relevant `$/SPLEBASE/etc/conf` (`%SPLEBASE%\etc\conf` in Windows) subdirectory:

- Web Application Server - `log4j.properties`
- Business Application Server - `log4j.properties`

2. Add the following lines to the file:

```
### E1 is an EmailAppender
log4j.appender.E1 = org.apache.log4j.net.SMTPAppender
log4j.appender.E1.Threshold = ERROR log4j.appender.E1.layout = org.apache.log4j.PatternLayout
log4j.appender.E1.layout.ConversionPattern = %d{ISO8601} [%t] %-
5p
%c %x - %m%n log4j.appender.E1.From = <from>
log4j.appender.E1.SMTPHost = <SMTPHost> log4j.appender.E1.Subject = <subject> log4j.appender.E1.To = <to>
##
### The following settings are optional
##
log4j.appender.E1.SMTPUsername = <SMTPUsername>
log4j.appender.E1.SMTPPassword = <SMTPPassword>
log4j.appender.E1.CC = <cc>
log4j.appender.E1.BCC = <bcc>
```

Parameter	Field from example	Usage
From	<from>	Email address for emails
To	<to>	Email address/group to send emails to
CC	<cc>	Email address/group to send courtesy copy of emails to
BCC	<bcc>	Email address/group to send "blind" courtesy copy of emails to
SMTPHost	<SMTPHost>	Host Name of SMTP Server
SMTPUsername	<SMTPUsername>	Logon User for SMTP Server (if supported)
SMTPPassword	<SMTPPassword>	Password for Logon User for SMTP Server (if supported)
Subject	<subject>	Subject for email message

3. Modify the following lines in the log4j.properties file:

```
## System-wide settings
# set log levels - for more verbose logging change 'info' to
'debug' ####
log4j.rootCategory=info, A1, F1, E1
```

4. Execute the initialSetup utility, with the -w option, to reflect the changes in the WAR/EAR file.
 5. To deploy the application refer to the Web Application Server Deployment Process or Business Application Server Deployment Process.

6.2 Overriding the Default Oracle Database Connection Information

By default the database connection for Oracle databases is of the format:

`jdbc:oracle:thin:@<hostname>:<dbport>:<database_sid>`

where:

Command Line Option	Description
<hostname>	Database hostname
<dbport>	Database Listener portname
<database_sid>	Database Name

The URL format is described at http://www.oracle.com/technology/tech/java/sqlj_jdbc/htdocs/jdbc_faq.html#05_03

This configuration setting is sufficient for the majority of the environments at a site. If your site requires a specialist URL for RAC support then you must override the default URL.

To override the default URL specify the following:

- Log on to the server containing the Business application server using the administration account for the desired environment (for example, splsys).
- Execute the `splenviro` utility, with the `-e` option, to attach to the desired environment to change.
- Execute the `configureEnv` utility and choose to change menu block 4 (Database).
- Change the Database Override Connection String to the desired custom JDBC url.
- Press `p` to save the change to the `ENVIRON.INI`.
- Execute `initialSetup`, with the `-t` option, to reflect the change in the `hibernate.properties` files. This may overwrite custom changes if custom templates are not used.
- Execute `initialSetup`, with the `-w` option, to include the configuration changes in the WAR/EAR files. This option is not required if externalization of configuration is implemented.
- For selected platforms redeployment of the WAR/EAR files is required as per Business Application Server deployment process.

The following example uses the Oracle JDBC thin client (for Oracle Real Application Clustering):

```
jdbc:oracle:thin:@(DESCRIPTION = (ADDRESS = (PROTOCOL = TCP)(HOST = machine-name)(PORT = 1251))
(ADDRESS = (PROTOCOL = TCP)(HOST = machine-name)(PORT = 1251)
(LOAD_BALANCE = yes)
(FAILOVER=YES)
(CONNECT_DATA =
(SERVER = DEDICATED)
(SERVICE_NAME = SID.WORLD)
)
)
```

Refer to Oracle RAC support for other examples. Example URL using the Oracle JDBC thick client:

`jdbc:oracle:oci:@SID.WORLD`.

Note:

For thick client to work, the Oracle client library directory must be added to the library search path. Oracle client libraries are installed under `ORACLE_HOME/lib` and `ORACLE_HOME/lib32` directories. Add this directory to the library search path environment variable. The library search path environment for AIX is `LIBPATH`, for HP-UX is `SH_LIB_PATH` for Linux is `LD_LIBRARY_PATH` and for Windows is `PATH`.

For Oracle Database 12.1 and above, use the format: `jdbc:oracle:thin:@<hostname>:<dbport>/<database_service>` to use Pluggable Databases where `<database service>` is the PDB name.

6.3 Cache Management

Note: If cache management requires global cache management across various nodes then refer to the [Global Cache Flush Support](#) section for more details.

A great deal of information in the system changes infrequently. In order to avoid accessing the database every time this type of information is required by an end-user, the system maintains a cache of static information on the Web Application Server. In addition to the Web Application Server cache, information is also cached on each client browser.

6.3.1 Server Cache

Note: Maintenance of the cache is performed automatically by the product. Whilst there are commands to force refreshes of the cache, these are designed for administrator and developer use only. Additional security setup is required to enable individual users to access to the facilities below.

The cache is populated the first time any user accesses a page that contains cached information. For example, consider a control table whose contents appear in a dropdown on various pages. When a user opens one of these pages, the system verifies that the list of records exists in the cache. If so, it uses the values in the cache. If not, it accesses the database to retrieve the records and saves them in the cache. In other words, the records for this control table are put into the cache the first time they are used by any user. The next user who opens one of these pages will have the records for this control table retrieved from the cache (thus obviating the database access).

The following points describe the type of data that is cached on the web server:

- **Field labels:** This portion of the cache contains the labels that prefix fields on the various pages in the system.
- **System information:** This portion of the cache contains installation and license key information as well as basic information about the various application services (e.g., the URL's that are associated with the various pages).
- **Menu items:** This portion of the cache contains the menu items.
- **Dropdown contents:** This portion of the cache contains the contents of the various dropdowns that appear throughout the system.
- **XSL documents:** This portion of the cache contains each page's static **HTML**.
- **Portal information:** This portion of the cache contains information about which zones are shown on the various pages.

The contents of the cache are cleared whenever the Web Application Server is restarted or as automatically refreshed as controlled by the `fieldValuesAge` parameter on the Web Application Server `web.xml` configuration file. This means that fresh values are retrieved from the database upon first use by end users.

If you change the database after the cache is built and the information you changed is kept in the cache, users may continue to see the old values. If you don't want to restart your Web Application Server, you can either use the relevant operation on the JMX FlushBean Mbean available on the Web Application Server or issue a custom browser URL to issue the appropriate command (see below).

Note: To use the browser URL for the resetting of the cache the user must be logged on to the product browser interface and have access to the `F1ADMIN` application service.

Function	JSP	MBean Operation
Refresh all cache	flushAll.jsp	flushAll
Refresh all drop down data	flushDropdownCache.jsp	flushDropDownCache
Refresh field labels	flushMessageCatalog.jsp	flushMessageCatalog
Refresh Fields and FK information	flushFieldAndFKMetaData.jsp	flushFieldAndFKMetaData
Refresh menu items	flushMenu.jsp	flushMenu Refresh
messages	flushMessaging.jsp	flushMessaging Refresh
navigation keys	flushNavigationInfo.jsp	flushNavigationInfo
Refresh portals and zones	flushportalMetaInfo.jsp	flushportalMetaInfo
Refresh screen style sheets	flushUI_XSLs.jsp	flushUIXSLs
Refresh security	flushSystemLoginInfo.jsp	flushSystemLoginInfo
Refresh specific drop down data	flushDropDownField.jsp	flushDropDownField

Note:

It is recommended that the "Refresh all cache" is used for non-production and production systems. The other commands are designed for primarily for development use only. Refer to the Oracle Utilities SDK documentation for more information about the options available with the commands.

When using these commands the cache will be reloaded over time with fresh data. As the data is loaded there is a negligible delay in each transaction that reloads data into the cache for the first time. Therefore it is recommended not to execute this command frequently.

6.3.2 Client Cache

In addition to the server cache, information is cached on each user browser. After clearing the cache that is maintained on the Web Application Server, it is recommended to also clear the cache that is maintained on the client browser (if possible). To do this, follow the following steps:

Browser	Steps
Microsoft Internet Explorer	<ul style="list-style-type: none"> • Select Tools on your browser menu bar. • Select Internet Options on the menu that appears. • Click the Delete Files button on the pop-up that appears. • Click the Delete all... button on the subsequent pop-up that appears and then click OK. • Enter the standard product URL to re-invoke the product.

Browser	Steps
Mozilla Firefox	<ul style="list-style-type: none"> • Select Tools from your browser menu bar. • Click Options on the Tools menu. • Select the Advanced tab from the Options dialog. • Select the Network tab from the Advanced tab. • Click on the Clear Now button. • Enter the standard product URL to re-invoke the product.

Note: Each user's cache is automatically refreshed as controlled by the `maxAge` and `maxAgeI` parameters in the Web Application Server `web.xml` configuration file. We recommend that you set these parameters to 1 second on development/test environments and 28800 seconds (8 hours) on production environments.

6.4 Oracle WebLogic: Expanded or Archive Format

Note: Expanded format is not support on IBM WebSphere or IBM WebSphere ND.

By default, the product is built into a set of WAR/EAR files and deployed in this format on Oracle WebLogic and IBM WebSphere/ND to operate. For Oracle WebLogic it is possible to use expanded mode rather than the WAR/EAR format. This mode allows the Oracle WebLogic instance directories access to the directories and files used by the J2EE components of the product without the need for WAR/EAR files. This has a number of key advantages:

- Changes to the individual files in the product (such as JSP's or graphics) do not require a rebuild of the WAR/EAR file.
- Outage time to deploy and execute the WAR/EAR file is reduced as Oracle WebLogic reads the files directly. In the deployment process, Oracle WebLogic loads the WAR/EAR file and uncompressed it to a staging or temporary location for actual execution. This is greatly reduced under expanded mode as the files are already uncompressed.
- Application of patches and service packs is faster as the patch installer does not need to rebuild the WAR/EAR files after applying patches.

This expanded mode is suggested for non-production and demonstration environments and is not recommended for production (the default is Archive [non-expanded] mode) as the during the WAR/EAR process additional integrity checks are performed and security control of individual application files adds higher security requirements to production.

The figure below illustrates the expanded mode main directories:




Figure 39: Expanded Format

- Under the `root` directory are the product specific subdirectories for each subsystem or part of the online component of the product.
- Under the `XAIApp` directory are the product specific subdirectories for each subsystem or part of the Web Services component of the product.
- Under the `businessapp` directory are the business object specific files for each subsystem or part of the online component of the product.
- The `help` and `AppViewer` directories contain an expanded mode version of the help HTML (and related files) and `appViewer` generated files (after running `genappvieweritems`).
- Under the `MCPApp` directory are the Mobile Communications Platform specific files (if the mobile framework is deployed with your product). **MOB**
- Under the `SPLAdfApp` directory are any ADF specific files if the Oracle ADF interface is installed and used with your product.

6.5 Implementing Custom Templates

As described in the Web Application Server Configuration Process and Business Application Server Configuration Process the configuration files used in the product are built from templates. These templates are typically located in the `SPLEBASE/templates` (or `%SPLEBASE%\templates` on Windows) subdirectory of each environment.

Note: The file `FW_template_structure.xml` in the `structures` subdirectory lists all the templates and their destination paths. This file should not be altered unless instructed by Oracle Support.

By default the product uses the base produce provided templates to build the configuration files. These configuration files are usually adequate for most needs in non-production but usually require some

customization for production or site specific standards not covered by the base templates. In the past the site had two options:

- **Make custom changes to the configuration file directly** – This can be performed against the \$SPLEBASE/etc/conf (%SPLEBASE%\etc\conf on Windows) copies of the configuration files. The issue here is that if the configuration files are reset back to the templates intentionally or unintentionally, using the initialSetup utility, custom manual changes may be lost if not reapplied manually.
- **Make custom changes to base configuration templates** – In extreme conditions it was possible to make manual changes to the base product templates to reflect your site standards and customizations. The issue is that new releases of the templates for new features would overwrite any customizations if not reapplied manually.

To address this it is now possible to override base product templates with a copy of the template (a custom template). This can be achieved by copying the desired base template in the templates directory to the same name prefixed with "cm.". The initialSetup utility will use the custom template instead of the base template.

The process to implement this is as follows:

- Identify the template that is used by the desired configuration file. Use the information in the Web Application Server Configuration Process and Business Application Server Configuration Process sections of this document to help identify the templates used for each configuration file.
- Copy the desired template in the \$SPLEBASE/templates (or %SPLEBASE%\templates on Windows) subdirectory to the same name but prefixed with a "cm.". This will be the override custom template. To disable the custom template at any time either rename the template to another name or remove it from the subdirectory.
- Make the necessary adjustments to the custom template as per your site standards. Please follow any conventions used in the template including use of environment variables or configuration settings from ENVIRON.INI.
- Use initialSetup as per Web Application Server Configuration Process and Business Application Server Configuration Process sections of this document to use the template to generate the new configuration files and incorporate the changes in the product.

Note: If custom templates are implemented, it is the site's responsibility to maintain the custom templates to reflect any changes in the base templates for new, changed or removed functionality.

6.5.1 Additional Templates

The templates mentioned previously in this document are the main configuration file based templates. There are additional configuration files that are built and used for various purposes. Most of these configuration files are used internally for management of the infrastructure and generation of utilities.

Note: The file FW_template_structure.xml in the structures subdirectory lists all the templates and their destination paths. This file should not be altered unless instructed by Oracle Support.

There are a number of areas the templates cover:

- **Configuration Files for Oracle WebLogic** – Oracle WebLogic has specific requirements for configuration settings and files. Refer to Oracle WebLogic Configuration Support for more specific details.
- **Configuration Files for other software** – Third party software has specific requirements for configuration files.
- **Utilities for deployment** – Additional configuration files are built to use in the deployment process to define the product applications to the relevant runtime software.
- **Internal ANT build configuration files** – Configuration and build files are built to support the configuration build process.

Note: The latter two categories of templates and configurations (utilities and ANT build files) should not be altered unless instructed by Oracle Support.

The table below lists the templates in the template directory not covered by other sections of this document applicable to the online, service and XAI components:

Templates	Configuration File	Usage
application.xml.template	application_web.xml	J2EE global application configuration file, which contains common settings for the Web Application Server.
application_service.xml.template	application_service.xml	J2EE global application configuration file, which contains common settings for the Business Application Server.
billdirfile.ini.template	billdirfile.ini	Bill Print extract configuration file
boot.properties.template	boot.properties	Oracle WebLogic boot credentials file used for starting server.
coherence-cache-config.xml.template	coherence-cache-config.xml	Batch Coherence cache settings. BATCH
config.xml.template config.xml.win.template	config.xml	Oracle WebLogic main configuration file. The win.template is used for the Windows environments.
doc1dirfile.ini.template	doc1dirfile.ini	Bill Print extract configuration file.
e0Batch.properties.template	e0Batch.properties	Global batch properties BATCH
earServiceBuild.xml.template	earServiceBuild.xml	ANT Build file for EAR file for Business Application Server.
earWebBuild.xml.template	earWebBuild.xml	ANT Build file for EAR file for Web Application Server.
ejb-jar.xml.template	ejb-jar.xml	Generic Business Application Server descriptor for EJB's.
Fault.xsd.iws.template	Fault.xsd	Web Services Fault Schema.

Templates	Configuration File	Usage
ibm-application-bnd.xmi.template	ibm-application-bnd.xmi	Deployment descriptor for IBM WebSphere/ND.
iws-build-common.xml.iws.template	iws-build.xml	Common settings for IWS Build.
iws-build-WAS.xml.iws.template	iws-build.xml	IWS build Settings for IBM WebSphere.
iws-build-WLS.xml.iws.template	iws-build.xml	IWS build Settings for Oracle WebLogic.
iwsdeploy-log4j.properties.iws.template	log4j.properties	Log properties for IWS build process.
jarservice.xml.template	jarservice.xml	ANT Build file for jar files.
java.login.config.template	java.login.config	JAAS Login file.
jps-config.xml.template	jps-config.xml	ADF security configuration.
log4j.properties.iws.template	log4j.properties	Log configuration for IWS.
log4j.properties.service.template	log4j.properties	Log configuration for BAS.
log4j.properties.standalone.template	log4j.properties	Log configuration for batch.
log4j.properties.template	log4j.properties	Log configuration for online.
log4j.properties.XAIApp.template	log4j.properties	Log configuration for XAI.
ouaf.jmx.access.file.template	ouaf.jmx.access.file	Default access file for JMX.
ouaf.jmx.password.file.template	ouaf.jmx.password.file	Default security file for JMX.
OUAF-Target.xml.template	OUAF-Target.xml	Oracle Identity Manager interface configuration File. Refer Doc ID: 970785.1 to My Oracle Support for details of this integration.
setDomainEnv.cmd.template	setDomainEnv.cmd	Utility to set Domain configuration for Oracle WebLogic on Windows
setEnv.sh.template	setEnv.sh	Utility to set Oracle WebLogic environment variables.
startWebLogic.cmd.template	startWebLogic.cmd	Utility to start Oracle WebLogic on Windows.

Templates	Configuration File	Usage
startWebLogic.sh.template	startWebLogic.sh	Utility to start Oracle WebLogic on Linux/UNIX.
startWLS.sh.template	startWLS.sh	Utility invoking JVM for Oracle WebLogic.
stopWebLogic.cmd.template	stopWebLogic.cmd	Utility to stop Oracle WebLogic on Windows.
system-jazn-data.xml.template	system-jazn-data.xml	ADF security store definitions.
tangasol-coherence-override.xml.template	tangasol-coherence-override.xml	Batch Coherence Overrides BATCH
warbuild.xml.template	warbuild.xml	ANT WAR Build file.
warupdate.xml.template	warupdate.xml	ANT WAR file for updates.
weblogic.policy.template	weblogic.policy	Java Security file used by Oracle WebLogic to protect the product files.
weblogic-ejb-jar.xml.template	weblogic-ejb-jar.xml	Deployment descriptor for Business Application Server for Oracle WebLogic.
XAIParameterInfo.xml.template	XAIParameterInfo.xml	XAI Configuration file.

Note: Templates not mentioned in this document that exist in the templates directory are included in one or more templates above depending on the configuration requirements.

6.6 Sending Emails at the Conclusion of Batch Process **BATCH**

It is possible to send a notification email when a batch process has ended. This notification happens after the batch process has ended and all application-related commits/rollbacks have taken place. It does not impact the batch process itself in the event of errors happening during the notification process. The default email is a simple text email that contains the batch control, date and time of the submission, run number, submission parameters, batch process summary indicating records processed and in-error, as well as the thread details, including logged messages (up to 100).

The email address can be an individual person or a valid mail group (the latter requires additional configuration in your email system).

To use email notification the email server must be configured using one of the following options:

- The mail server can be defined through the default Message Sender (Class `RTEMAILSNDR`) with the appropriate SMTP settings on the Context tab.

- Alternatively the properties can be supplied in the form of JVM properties as follows:

```

# Host whose mail services will be used
# (Default value: localhost)
mail.host=<your mail server>

# Return address to appear on emails
# (Default value: username@host)
mail.from=<name@host>

# Other possible items include:
# mail.user=
# mail.store.protocol=
# mail.transport.protocol=
# mail.smtp.host=
# mail.smtp.user=
# mail.debug=

```

Name	Type	Description
mail.debug	boolean	The initial debug mode. Default is false.
mail.from	String	The return email address of the current user, used by the <code>InternetAddress</code> method <code>getLocalAddress</code> . To ensure that the value of <code>mail.from</code> property is handled properly when set through a user exit include file, add a '\' (backslash) in front of the '@' symbol. e.g. If the value desired for <code>mail.from</code> is <code>demo@orgname.org</code> then it should be set as <code>demo\@orgname.org</code>
mail.host	String	The default host name of the mail server for both Stores and Transports. Used if the <code>mail.protocol.host</code> property isn't set.
mail.mime.address.strict	boolean	The <code>MimeMessage</code> class uses the <code>InternetAddress</code> method <code>parseHeader</code> to parse headers in messages. This property controls the strict flag passed to the <code>parseHeader</code> method. The default is true.

Name	Type	Description
mail.smtp.class	String	Specifies the fully qualified class name of the provider for the specified protocol. Used in cases where more than one provider for a given protocol exists; this property can be used to specify which provider to use by default. The provider must still be listed in a configuration file.
mail.smtp.host	String	The host name of the mail server for the specified protocol. Overrides the <code>mail.host</code> property.
mail.smtp.port	int	The port number of the mail server for the specified protocol. If not specified the protocol's default port number is used.
mail.smtp.user	String	The user name to use when connecting to mail servers using the specified protocol. Overrides the <code>mail.user</code> property.
mail.store.protocol	String	Specifies the default message access protocol. The <code>Session</code> method <code>getStore()</code> returns a <code>Store</code> object that implements this protocol. By default the first <code>Store</code> provider in the configuration files is returned.
mail.transport.protocol	String	Specifies the default message access protocol. The <code>Session</code> method <code>getTransport()</code> returns a <code>Transport</code> object that implements this protocol. By default the first <code>Transport</code> provider in the configuration files is returned.
mail.user	String	The default user name to use when connecting to the mail server. Used if the <code>mail.protocol.user</code> property isn't set.

These properties can be added to the `threadpoolworker.properties` file for the standalone batch `threadpoolworker`, or the `spl.properties` file for an online application server that hosts a batch worker.

6.7 Oracle WebLogic Configuration Support

Whilst the product supports multiple J2EE Web Application Server vendors, the product has native support for Oracle WebLogic. Normally the J2EE Web Application is installed and the J2EE Web Application Server components are embedded in the directories controlled by the Web Application Server software during the deployment process. The deployment process usually transfers the WAR/EAR files to the J2EE Web Application Server directories (varies according to J2EE Web Application Server software).

For Oracle WebLogic, the Oracle WebLogic software is effectively pointed to directories as in the product installation. This avoids Oracle WebLogic having additional copies of its configuration and WAR/EAR files under its own directory structure.

In this case the following configuration aspects of Oracle WebLogic apply:

- The `$SPLBASE/splapp` (or `%SPLBASE%\splapp` in Windows) subdirectory is referenced directly in the configuration files.
- In non-expanded mode (see Oracle WebLogic: Expanded or Archive Format for details), the WAR/EAR files are directly referenced from the `config.xml` file.
- In expanded mode (see Oracle WebLogic: Expanded or Archive Format for details), the application files are directly referenced in the `splapp` subdirectories from the `config.xml` file.
- The `config.xml` file is located under `splapp/config` rather than using the Oracle WebLogic location. Any changes made from the Oracle WebLogic console are stored in this file.
- The utilities to start and stop the Oracle WebLogic instance are located under the `splapp` subdirectory.
- The security configuration files for the Oracle WebLogic instance are located under the `splapp` subdirectory. The security repository configured is configured in the location supplied with the Oracle WebLogic instance.

Thus, this facility allows one installation of Oracle WebLogic to be used across many environments with each environment being independent.

6.8 Using Configuration Files Outside the WAR/EAR File

Typically, the configuration files specified Web Application Server Configuration Process and Business Application Server Configuration Process are embedded into the WAR/EAR files, as per the J2EE specification, ready for deployment for use at runtime. While this is generally acceptable for most sites, it also means that any configuration change requires rebuilding of the WAR/EAR files and redeployment to fully implement the configuration changes. This may add outage time to implement configuration changes.

It is possible to allow the product to use versions of the certain configuration files outside the WAR/EAR files to minimize outage time to implement changes. In most cases, a restart of the product components is necessary to implement the configuration change.

The table below outlines the configuration files that can be externalized from the WAR/EAR file by product component:

Component	Configuration File	Externalized
Web Application Server (root and XAIApp)	<code>web.xml</code>	X
	<code>spl.properties</code>	✓
	<code>weblogic.xml</code>	X
	<code>log4j.properties</code>	✓
Business Application Server	<code>web.xml</code>	X

Component	Configuration File	Externalized
	spl.properties	✓
	hibernate.properties	✓
	log4j.properties	✓

By default, the externalization works on the following principles:

- The `SPLEBASE` environment variable must be set to the home location of the software prior to execution of the Web Application Server or Business Application Server. This must match the value configured for the environment in the `cistab` configuration file on the machine.
- The external versions of the configuration files should be in their default locations (as supplied) in the `$SPLEBASE/etc/conf` (or `%SPLEBASE%\etc\conf` for Windows) subdirectories.
- The product use the external configuration file versions instead of the versions embedded in the WAR/EAR files. If you wish to revert to the embedded versions then the site can either rename the `conf` subdirectories to prevent the external configuration files being detected or ensuring the `SPLEBASE` environment is not set.

Warning: If the `conf` subdirectories are renamed they should be reverted to their original names before ANY single fix, service pack or upgrade is performed to prevent configuration reset to base templates or installation failure.

This facility is useful for a number of situations:

- If any passwords are changed that are used by the product on a regular basis, reflecting changes in the configuration files directly or using templates is easier using externalized configuration files. The WAR/EAR files do not need to be rebuilt and redeployed and this can save time.
- During the initial phases of production or when traffic volumes fluctuate, it may be necessary to tune specific settings. This allows experimentation of the changes before committing to specific values. It allows greater level of flexibility in configuration change.

Note: It is recommended to ensure that in the long term that both the external versions and embedded versions are kept in synch on a regular basis to prevent configuration issues. This can be done using standard maintenance windows as necessary.

6.9 Oracle RAC Support

Note: Refer to the Oracle Real Application Clustering (RAC) documentation for setup instructions and parameter settings for RAC. It is assumed that RAC is installed, including Oracle Notification Service (ONS) for Fast Connection Failover support and configured prior to configuration of the product to take advantage of the RAC installation.

The product supports the use of Oracle's Real Application Clustering (RAC) for high availability and performance through database clustering. The product has additional setting to tell the database pooling aspects of the product to take advantage of the RAC facilities. Once RAC has been installed and configured on the database there are a number of options that can be used to configure the product to use RAC in all modes of configuration:

- It is possible to setup a custom DB Connection string to take advantage of the RAC as outlined in the Overriding the default Oracle database connection information section of this document. This is the easiest implementation of RAC but does not take advantage of the full RAC features.
- Configure RAC specific settings in the installation configuration files (via the `configureEnv[.sh]` utility).

The following settings should be set:

Environment Setting	Usage	Comments
ONS_JAR_DIR	Location of ONS Jar file (<code>ons.jar</code>)	This is the location of the Oracle Notification Service Jar files for use in the product.
ONS CONFIG	ONS configuration string with RAC server nodes delimited by "," in the form <code><host>:<port></code> where <code><host></code> is the RAC host node and <code><port></code> is the ONS listener port.	Used for connections

Note:

Native RAC Support does not support XA transactions using Universal Connection Pool (UCP) at the present time. If XA compliance is required, it is suggested that JNDI based pools provided by the Web Application server be used as documented in Using JNDI Based Data Sources.

At the present time Oracle Single Client Access Name (SCAN) is not supported in the configuration of RAC native support.

Once the `spl.runtime.options.isFCFEnabled` option is set to true and `spl.runtime.options.onsserver` is set to the value specified in ONS CONFIG.

Support for Implicit Connection Caching has been removed as this feature has been superseded by Universal Connection Pool (UCP).

6.10 Adding a Custom Privacy Policy Screen

In certain sites the product must display a privacy policy to remind users of privacy rules at a site. The product allows for a custom HTML based page to be added by the site. The privacy page should be named `privacy.html` and placed in the `cm` directory. You can access the `privacy.html` using the following url:

<https://<host>:<port>/<server>/cm/privacy.html>

Where,

Command Line Option	Description
<code><host></code>	Host Name of the Web Application Server used by the product
<code><port></code>	Port Number allocated to the Web Application Server used by the product

Command Line Option	Description
<server>	Server context allocated to Web Application Server used by the product

Refer to the Oracle Utilities SDK on how to add custom HTML to the product.

Once implemented the privacy statement can be obtained from the above URL or from the following URL:

<http://<host>:<port>/<server>/privacy>

Where,

Command Line Option	Description
<host>	Host Name of the Web Application Server used by the product
<port>	Port Number allocated to the Web Application Server used by the product
<server>	Server context allocated to Web Application Server used by the product

6.11 IBM WebSphere/IBM WebSphere ND Support

Whilst the product supports both Oracle WebLogic and IBM WebSphere there are specific additional options available for IBM WebSphere and IBM WebSphere ND. The list below summarizes the specific additional support for these Web Application Servers:

- The application within IBM WebSphere is set to the following values:

Tier	Usage
Web Application Server	SPLWeb-<WEB_SVRNAME> where <WEB_SVRNAME> is the value of the WEB_SVRNAME environment setting.
Business Application Server	SPLService-<BSN_SVRNAME> where <BSN_SVRNAME> is the value of the BSN_SVRNAME environment setting.

The following IBM WebSphere specific environment settings (ENVIRON.INI) should be specified for correct basic operation:

Environment Setting	IBM WebSphere edition
BSN_APP (SPLService)	WAS WASND
BSN_NODENAME	WASND
BSN_SRVNAME	WAS WASND
BSN_WLHOST	WAS WASND
WAS_HOME	WAS

Environment Setting	IBM WebSphere edition
WASND_DMGR_HOST	WASND
WASND_HOME	WASND
WEB_APP (SPLWeb)	WAS WASND
WEB_NODENAME	WASND
WEB_SVRNAME	WAS WASND
WEB_WLHOST	WAS WASND

These variables are used by the `initialSetup` utility to build and deploy the EAR/WAR files correctly.

- A number of Python scripts are used by the utilities to interface to IBM WebSphere administration API:

Command Script	Usage
<code>websphereDeployService.py</code>	Deploy Business Application Service WAS
<code>websphereDeployWeb.py</code>	Deploy Web Application Service WAS
<code>websphereNDDeployService.py</code>	Deploy Business Application Service WASND
<code>websphereNDDeployWeb.py</code>	Deploy Web Application Service WASND
<code>websphereNDStartService.py</code>	Start Business Application Service WASND
<code>websphereNDStartWeb.py</code>	Start Web Application Service WASND
<code>websphereNDStopService.py</code>	Stop Business Application Service WASND
<code>websphereNDStopWeb.py</code>	Stop Web Application Service WASND
<code>websphereNDUndeployService.py</code>	Undeploy Business Application Service WASND
<code>websphereNDUndeployWeb.py</code>	Undeploy Web Application Service WASND
<code>websphereStartService.py</code>	Start Business Application Service WAS
<code>websphereStartWeb.py</code>	Start Web Application Service WAS
<code>websphereStopService.py</code>	Stop Business Application Service WAS
<code>websphereStopWeb.py</code>	Stop Web Application Service WAS
<code>websphereUnDeployService.py</code>	Undeploy Business Application Service WAS
<code>websphereUnDeployWeb.py</code>	Undeploy Web Application Service WAS

- The utilities to deploy/undeploy (`initialSetup`) the Web and Business Application WAR/EAR files and start/stop the server (`spl`) utilize the IBM WebSphere `wsadmin` command. Refer to the IBM WebSphere/ND documentation for more details of this command.
- The `initialSetup` utility, provided with the product, operate at the node level and not the cluster level for IBM WebSphere/ND. Customers wanting to deploy/undeploy at the cluster level should use the `wsadmin` command natively or use the IBM WebSphere administration console to achieve this.

6.12 User Exit Include Files

Whilst the product supports custom templates it is now possible to only supply fragments of a customization rather than whole configuration templates, known as user exit include files. This allows you to specify additional settings to be included in the templates provided in stream when the product templates are used to generate the configuration files when using the `initialSetup` command.

When `initialSetup` is executed the templates are applied with the following order of preference:

- Base framework templates (no prefix). These templates should not be altered.
- If a product specific template exists (prefixed by the product code) then the product template is used instead of the base Framework template for the configuration file. These templates should not be altered.
- If a template is prefixed with "cm_" then this is a custom template to be used instead of the product specific and base framework template.

These templates should live in `$SPLEBASE/templates` (or `%SPLEBASE%\templates` on Windows).

Note: When creating custom templates please use the base framework and any related product templates as the basis for the content of the custom template.

Whilst this facility is flexible it means that any updates to the base or product templates MUST be reflected in any custom templates. A new option is to use user exits that are placed strategically in the most common configuration files that need change. When `initialSetup` is executed the existence of user exit files are checked (when an `#ouaf_user_exit` directive exists in the template) and the contents included in the generated configuration file. The figure illustrates the process for a typical configuration change:




Figure 40: Include Files

As with the custom templates user exits have preferences depending on the ownership of the user exit include file. Custom includes will override any product specific includes. There are no base includes as they are already included in the template files. The figure below illustrates the preferences for both templates and includes:




Figure 41: Template Hierarchy

The table below outlines the currently available user exits in the available templates:

Template File	User Exit Include file	Position and Usage
boot.properties.template	boot.properties.exit.include	Used to change boot properties file from Oracle WebLogic
config.xml.template ²⁰	config.xml.exit_1.include	Before ADF deployment information (used for ADF)
	config.xml.exit_2.include	After Web Application container definition
	config.xml.exit_3.include	End of Configuration File
	config.xml.exit_4.include	Before Web Application container definition
	config.xml.jms.include	WebLogic JMS Configuration
config.xml.win.template ²¹	config.xml.win.exit_1.include	Before ADF deployment information (used for ADF)
	config.xml.win.exit_2.include	After Web Application container definition
	config.xml.win.exit_3.include	End of Configuration File
	config.xml.win.exit_4.include	Before Web Application container definition
	config.xml.win.jms.include	WebLogic JMS Configuration
ejb-jar.xml.template	ejb-jar.xml.wls.jms_1.include	JMS Mappings for Oracle WebLogic
	ejb-jar.xml.was.jms_1.include	JMS Mappings for IBM WebSphere/ND
hibernate.properties.web.template	hibernate.properties.exit.include	At end of file (common hibernate.properties entries)
	hibernate.properties.web.exit.include	At end of file (online specific hibernate.properties entries)
log4j.properties.template	log4j.properties.exit.include	At end of file (common log4j.properties entries)
	log4j.properties.root.exit.include	At end of file (specific online log4j.properties entries)
log4j.properties.XAIApp.template	log4j.properties.exit.include	At end of file (common log4j.properties entries)

²⁰ This is the template for the Oracle WebLogic instance; refer to the Oracle WebLogic for an example of contents.

²¹ This is the template for Windows version of Oracle WebLogic.

Template File	User Exit Include file	Position and Usage
	log4j.properties.XAIApp.exit.include	At end of file (specific XAI log4j.properties entries)
log4j.properties.service.template	log4j.properties.exit.include	At end of file (common log4j.properties entries)
	log4j.properties.service.exit.include	At end of file (specific XAI log4j.properties entries)
ouaf.jmx.access.file.template	ouaf.jmx.access.file.exit.include	Allows for additional users to be specified for JMX connections
ouaf.jmx.password.file.template	ouaf.jmx.password.file.exit.include	Allows for additional passwords to be specified for JMX users
spl.properties.service.template	spl.properties.exit.include	At end of file (common spl.properties entries)
	spl.properties.service.exit.include	At end of file for EJB spl.properties entries.
	spl.properties.service.timouts.exit.include	User exit for service timeouts.
spl.properties.template	spl.properties.exit.include	At end of file (common spl.properties entries)
	spl.properties.root.exit.include	At end of file for Web Application based spl.properties entries.
	spl.properties.timouts.root.exit.include	User exit for global timeouts
spl.properties.XAIApp.template	spl.properties.exit.include	At end of file (common spl.properties entries)
	spl.properties.XAIApp.exit.include	At end of file for XAI Application based spl.properties entries.
	spl.properties.XAIApp.timouts.exit.include	Future use
submitmitbatch.properties.template	submitbatch.properties.exit.include	Submitter extensions
threadpoolworker.properties.template	threadpoolworker.properties.exit.include	Threadpool extensions
web.xml.template	spl.properties.images.include	Image processing overrides for web.xml
	web.xml.servlet_mapping.include	Allow custom servlet mappings
	web.xml.servlet.include	Allow custom servlet definitions
	spl.properties.filter_mapping.include	Allow custom filter mappings

To use these user exits create the user exit include file with the prefix "cm_" in the \$SPLBASE/templates (or %SPLBASE%\templates) directory. To reflect the user exits in the configuration files you must execute the initialSetup utility. Refer to the Custom JMS Configuration section for an example of this process.

6.12.1 Properties File User Exits

The product behavior is controlled at a technical level by the values in the properties files. Whilst most of the settings are defaulted to their correct settings in the file, additional parameters may be added to the properties files to add new behavior. User exits are used to set these additional parameters in the properties files.

From the table above there are more than one user exit available in each properties file template to use. This is designed to maximize the reusability of configuration settings. There are a number of specialized user exits that may need to be used:

- **Common Settings** – The configuration files used by each channel of execution (online, Web Services and batch) has a common user exit. This user exit is used to house all the setting you want to implement regardless of the channel used. For example the common setting user exits are:

Configuration File	User Exits for Common Settings
hibernate.properties	hibernate.properties.exit.include
log4j.properties	log4j.properties.exit.include
spl.properties	spl.properties.exit.include

- **Channel Specific Settings** – To implement custom settings per channel there is a separate user exit to hold those parameters for those channels. The specific user exits are:

Channel	Configuration File	User Exits for Common Settings
Web App Server	hibernate.properties	hibernate.properties.web.exit.include
	log4j.properties	log4j.properties.root.exit.include
	spl.properties	spl.properties.root.exit.include
Business Server App	log4j.properties	log4j.properties.service.exit.include
	spl.properties	spl.properties.service.exit.include spl.properties.service.timeout.s.exit.include
XAI Web Services	log4j.properties	log4j.properties.XAIApp.exit.include
	spl.properties	spl.properties.XAIApp.exit.include
Inbound Web Services	log4j.properties	No User Exit available
	spl.properties	No User Exit available

Channel	Configuration File	User Exits for Common Settings
Batch BATCH	hibernate.properties	hibernate.properties.batch.exit.include
	log4j.properties	log4j.properties.standalone.exit.include
	spl.properties	spl.properties.standalone.exit.include spl.properties.timeouts.standalone.exit.include

6.13 Custom JMS Configuration

The product includes a realtime Java Message Services (JMS) connector to provide application to application integration. To use this facility the physical JMS definitions need to be defined as part of the configuration to be included in the configuration of the J2EE Web Application Server²². These will match the JMS configuration within the product itself. Refer to the installation documentation provided with the product to understand the required JMS integration.

To reflect the JMS settings a number of custom user exist include files have been provided to implement the JMS changes in the `config.xml` and `ejb-jar.xml` configuration files required by the J2EE Web Application Servers.

There are two sets of files that are provided for the JMS integration as examples:

- A set of user exit include files in the `scripts/cm_examples/FW/templates` directory for the various files necessary to define the physical JMS configuration settings.
- A set of sample XML files that define the attributes of sample JMS settings that are referred to by the custom templates user exit include files. These are the files that need to be maintained by the site according to product or local standards.

²² It is possible to define the physical JMS configuration using the console provided with the J2EE Web Application Server but this may be overwritten during upgrades.

The figure below illustrates the location of the sample JMS files:




Figure 42: Custom JMS Configuration

To implement the JMS configuration files at your site:

- Logon to the Web Application Server and/or Business Application Server machine using the product administration account.
- Execute the `splenvirion` command to orientate to the desired environment you wish to apply the JMS configuration to.
- Create a JMS configuration repository directory under `/splapp/config/jms`. The following:

Linux/UNIX:

```
mkdir -p $SPLEBASE/splapp/config/jms
```

Windows:

```
mkdir %SPLEBASE%\splapp\config\jms
```

- Copy the sample XML configuration files to the directory created using the following commands:

Linux/UNIX:

```
cp
$SPLEBASE/scripts/cm_examples/FW/splapp/config/jms/*$SPLEBASE/splapp/co
nfig/jms/
```

Windows:

```
xcopy
%SPLEBASE%\scripts\cm_examples\FW\splapp\config\jms\*%SPLEBASE%\splapp\
config\jms\
```

- Copy the user exit include files to the template directory so that the user exits are implemented whenever `initialSetup` is executed.

Linux/UNIX:

```
cp $SPLEBASE/scripts/cm_examples/FW/templates/*$SPLEBASE/templates/
```

Windows:

```
xcopy %SPLEBASE%\scripts\cm_examples\FW\templates\*%SPLEBASE%\templates
```

Note: To reverse out the change at any time the template files that are copied (prefixed by cm) can be removed from the templates subdirectory under `%SPLEBASE%` or `$SPLEBASE`.

- Modify the sample XML files in the `config/jms` directory to suit your product requirements or your site requirements.

At configuration time the settings provided these files are included in the target configuration files as indicated by the user exit include files.

6.14 Online Transaction Timeouts

By default the product does not impose any transaction time limits on online and web services transactions. If this is not appropriate for your site then transaction time limits can be implemented globally as well as on individual objects using configuration settings defining the desired transaction time limits.

Specific user exits should be used to maintain these settings. To implement these create or modify the user exit files indicated in the table below in `$SPLEBASE/templates` (or `%SPLEBASE%\templates` on Windows).

To impose global limits the following settings must be added to your user exit files:

Tier/Configuration File	Configuration Setting
Web Application Server (<code>cm_spl.properties.timeouts.root.exit.include</code> user exit file)	<ul style="list-style-type: none"> • Set the <code>ouaf.timeout.query.default</code> parameter to the desired timeout (in seconds) to set a global default on query zones.

Tier/Configuration File	Configuration Setting
Business Application Server <code>(cm_spl.properties.service.timeouts.exit.include user exit file)</code>	<ul style="list-style-type: none"> Set the <code>ouaf.timeout.business_service.default</code> parameter to the desired timeout (in seconds) to set a global default on business service invocations. Set the <code>ouaf.timeout.business_object.default</code> parameter to the desired timeout (in seconds) to set a global default on business object invocations. Set the <code>ouaf.timeout.script.default</code> parameter to the desired timeout (in seconds) to set a global default on service script invocations. Set the <code>ouaf.timeout.service.default</code> parameter to the desired timeout (in seconds) to set a global default on application service invocations.

To impose timeout values on individual object/service/scripts then an entry in the Business Application Server `cm_spl.properties.service.timeouts.exit.include user exit file` must exist for each individual object/service/script to specify the timeout:

Object	Comments
Business Objects	<u>Default:</u> <code>ouaf.timeout.business_object.default</code> . <u>Specific:</u> <code>ouaf.timeout.business_object.<bocode></code>
Business Services	<u>Default:</u> <code>ouaf.timeout.business_service.default</code> . <u>Specific:</u> <code>ouaf.timeout.business_service.<bscode></code>
Query Zones	<u>Default:</u> <code>ouaf.timeout.query.default</code> <u>Specific:</u> <code>ouaf.timeout.query.<zonenumber></code>

Object	Comments
Scripts	<u>Default:</u> ouaf.timeout.script.default. <u>Specific:</u> ouaf.timeout.script.<scriptname>
Application Services	<u>Default:</u> ouaf.timeout.service.default. <u>Specific:</u> ouaf.timeout.service.<service>

For example:

ouaf.timeout.service.CILTUSEP=600

Note:

Timeout values are not precise as they do not include additional time needed to process any rollback or networking activity necessary after a timeout has occurred.

Timeout user exits exist for batch and XAI as well but they are not used in the current release of the product. These are reserved for potential use in future releases.


6.15 Setting the Date for Testing Purposes

One of the common techniques used in testing is to set the date to a fixed point in time to simulate data aging in the product. By default, the date (and time) used in the system is obtained from the database server with the time zone used on the user record to offset (if used by the product). It is possible to override the system date used at a global level or at an individual user level for testing purposes.

Note: This facility is not recommended for use in Production environments.

To use this facility the following must be configured:


- Set the `spl.runtime.options.allowSystemDateOverride` to `true` in the `spl.properties` file for the online (Web or Business Application Server), XAI (Business Application Server) and/or Batch (standalone).
- To set the feature at the global level for an environment, navigate to the Administration menu → F → Feature Configuration menu option and add a General System Configuration Feature Type with the System Override Date option in `YYYY-MM-DD` format. For example:



The screenshot shows the 'Feature Configuration' screen with the 'Main' tab selected. A red box highlights the 'Feature Type' dropdown, which is set to 'General System Configuration'. Another red box highlights the 'System Override Date' dropdown in the 'Options' table, which is also set to 'System Override Date'. The table has columns for 'Option Type', 'Sequence', 'Value', and 'Detailed Description'. The detailed description states: 'This option provides a way to override the system date for on-line operations. Specify a system override date in the format YYYY-MM-DD. If populated, the system will use this date as the system date instead of retrieving the system date from the database.'

Figure 43: Feature Configuration

- If individual test users wish to use different dates they can set the feature at the user level. This feature does not require the global override setting to be used but if the global override is also used, then this user specific setting is used. To set the date override at the user level, add the Overridden system date Characteristic Type to the individual user record (via Administration menu → U → User menu option) with the Characteristic Value set to the desired date in YYYY-MM-DD format. For example:



The screenshot shows the 'User' screen with the 'Characteristics' tab selected. A red box highlights the 'Characteristics' tab. Another red box highlights the 'System Override Date' dropdown in the 'Characteristics' table, which is set to 'System Override Date'. The table has columns for 'Characteristic Type', 'Sequence', and 'Characteristic Value'.

Figure 44: System Override for Individual Users

When the facility is active the following applies:

- The facility will only be active if the `spl.runtime.options.allowSystemDateOverride` parameter is set to `true` in the relevant `spl.properties` file.
- If the system override via Feature configuration is set then all users using that channel will use that date for any transactions. If the Feature configuration is not set then the default current date as per the database server is used.
- If users have system date overrides as characteristics then that user for that channel will use that date regardless if the system override is set or not.

6.16 Secure Transactions

Note: Refer to the *Security Guide* for the product for an indepth discussion on implementing SSL.

The product supports HTTP and HTTPS protocols for transmission of data from the browser client and within the architecture. Customers must choose either HTTP (unsecure) or HTTPS (secured) for protocol. Use of both protocols simultaneously is not supported. The default protocol is HTTP.

If you wish to implement HTTPS protocol then the following process must be used:

- The value for `WEB_WLSSLPORT` must be specified for the SSL port to use. When this is specified then HTTP is disabled automatically.

- The product ships with the demonstration certificate shipped with the Web Application Server software. It is not recommended to use this certificate for your site. It is highly recommended that you obtain a certificate for your site from a trusted source and install the certificate as per the Web Application Server documentation.
- For all traffic directly to the product please use the `https` protocol on the URL's used for direct interaction (via the browser or Web Services interfaces).

Note:

For Oracle WebLogic customers, refer to the Configuring Identity and Trust section of the Oracle WebLogic Installation Guide.

For both protocols, the PUT, DELETE, TRACE and OPTIONS methods not permitted in the security constraints for the product by default.

6.17 Native Oracle WebLogic Support

Note:

The product also now supports the Oracle Fusion Middleware console as an alternative to the Oracle WebLogic console. This manual covers the Oracle WebLogic console only. Customers using the Fusion Middleware console should use the corresponding feature in that console. One of the features of the product is the ability to use the Oracle WebLogic features in either embedded or native mode. In non-production it is recommended to use embedded mode unless otherwise required. Customers using Oracle ExaLogic for non-production should use native mode to fully support Oracle ExaLogic's architecture.

Whilst all the details of installing the product in native mode is covered in the *Oracle Revenue Management and Billing Installation Guide* a summary of what is required is shown below:

- A copy of the Oracle WebLogic must be installed on the machine. This copy of Oracle WebLogic must not be shared across multiple environments. Using native mode restricts a single copy of the product to an individual installation of Oracle WebLogic. Customers requiring multiple environments on a single installation should use embedded mode or install multiple Oracle WebLogic installation and use Oracle Enterprise Manager to manage the multiple instances.

Note:

The product now includes a set of base [domain templates](#) that can be used with the installation of the product to avoid manual installation issues. [Domain Template Builder](#) can also be used to build custom domain templates.

- When using native mode, the product installation should not be placed under a user's home directory or under the Oracle WebLogic home location. It should be installed in a separate location and using the deployment utilities deployed into the Oracle WebLogic domain location.

- Oracle WebLogic must be setup and configured with the following before deployment is to be performed:

Configuration Setting	Comments
Domain should be created	The Oracle WebLogic domain to install the product upon should be created with the Administration Server active on that environment.
Servers should be created	Using the Oracle WebLogic console the Servers to house the product should be created.
Create XML Registry	Using the Oracle WebLogic console an XML Registry to define the default parser should be created. On AIX this is done at the Oracle WebLogic command line level. Refer to the <i>Oracle Revenue Management and Billing Installation Guide</i> for more details.
Set Java parameters in console	Set the Domain level java settings for memory etc as per the <i>Oracle Revenue Management and Billing Installation Guide</i> .
Define Security	Define the Security Role, Security Realm and other Security definitions for the product as per the <i>Oracle Revenue Management and Billing Installation Guide</i> .
Create SYSUSER	Create the initial User for the product (SYSUSER) and attach the security role created earlier.
Set SPLEBASE variable	Prior to deployment and execution ensure the SPLEBASE variable is set to point to the location of the product as per the <i>Oracle Revenue Management and Billing Installation Guide</i> .

- To start and stop the online component of the product, in native mode, it is recommended to use the facilities provided by Oracle WebLogic. This can be either using the Oracle WebLogic console, Oracle WebLogic utilities or via Oracle Enterprise Manager.
- To monitor the online component of the product use the facilities provided in Oracle WebLogic console, Oracle WebLogic utilities or via Oracle Enterprise Manager. Additional monitoring capabilities are available using the Oracle Application Management Pack for Oracle Utilities.

When making changes to the product anytime the EAR files are changed they must be redeployed using the Oracle WebLogic console.

6.17.1 Manual Re-Deployment Process

Whenever the installation EAR/WAR files are updated they must be redeployed to the J2EE Web Application Server to implement the change using one of the following techniques:

- Using the Oracle WebLogic console, use the Update transaction on the selected Deployments. The wizard will remember the last settings, which need to be confirmed, prior to deployment. For example:

Name	State	Health	Type	Targets	Deployment Order
SPLService	Active	OK	Enterprise Application	myserver	100
SPLWeb	Active	OK	Enterprise Application	myserver	200
Webservices	Active	OK	Web Application	myserver	100

Figure 45: Update Oracle WebLogic Deployment

- Use the WLST command line using the redeploy command in the Deployment API. Refer to the WLST Reference for more information.

The following situations require a redeployment event:

- Any execution of initialSetup or initialSetup -w which requires SPLService (or the value of SPLSERVICEAPP) and SPLWeb (or the value of SPLWEBAPP) to be redeployed.
- Any execution of iwsdeploy.sh or online deployment of Inbound Webservices. This requires Webservices (or the value of IWSWAR) deployment.

6.18 Oracle WebLogic Console Operations

Note: Parts of this section do not apply to implementations using the embedded mode. Refer to individual sections for guidance.

When using the native mode of Oracle WebLogic to manage the product, the Oracle WebLogic administration console can be used to perform common operations. This section outlines the common operations that can be used from the console. Refer to the Administration documentation supplied with Oracle WebLogic for further advice.

6.18.1 Starting and Stopping from Console

Note: This facility should only be used for customers using native mode. Customers using embedded mode should use the `spl` utility.

As the product is using the native mode and native utilities provided by Oracle WebLogic it is possible to manage the product start and stop from the console. To perform this function, the user must do the following:

- Login to the console designated to administrate the environment using an appropriate administration account²³.

²³ The default installation account is system if used.

- Select the Deployments section of the Domain Structure. This will list the deployments to the domain.
- Select the appropriate deployments to start or stop.
- Use the Start or Stop function to perform the start or stop operation, respectively.

For example:

Name	State	Health	Type	Targets	Deployment Order
SPLService	Active	OK	Enterprise Application	myserver	100
SPLWeb	Active	OK	Enterprise Application	myserver	200
Webservices	Active	OK	Web Application	myserver	100

Figure 46: Default Oracle WebLogic Deployments

While it is possible to start or stop individually components it is recommended that all components be started at once to avoid availability issues. If individual components are started or stopped use the following guidelines to minimize issues:

- Be aware of the architecture when stopping components. When starting the product, components lower in the architecture must be started first. When stopping the product, components higher in the architecture should be stopped first. Use the table below as a guide:

Deployment	Role
root	Web Application Server
SPLService	Business Application Server
XAIApp/Webservices	XML Application Integration
Help	Online Help
AppViewer	Data Dictionary

- Stopping non-essential runtime components such as Online Help and AppViewer may result in HTTP 404 error when users select these functions unless they are sourced from other servers.

6.18.2 Monitoring Web Applications Using the Console

Note: This facility is available regardless of mode (i.e. embedded or native) used on the environment.

The Oracle WebLogic administration console can be used to monitor the state and performance of the individual components of the product. This can be achieved using the Monitoring tab of the Deployments option of the Domain Structure section of the Oracle WebLogic administration console.

This allows the following to be monitored:

- **Web Applications** - Statistics relating to the Web Applications deployed to the server. The Context Root and Source Information outlines the individual component monitored.
- **JMS** - If you are using the Message Driven Bean functionality within the product to integrate to the JMS resources in the Oracle WebLogic server then statistics related to this function can be monitored.
- **EJBs** - The Business Application Server and Message Driven Bean functionality are expressed as Enterprise Java Beans (EJB) and can be monitored from the console. The EJB SPLServiceBean is the Business Application server.
- **Web Services/Web Service Clients** - When using the native Web Service capability the statistics applicable to individual Web Services can be monitored.
- **JDBC** - If JDBC data sources are manually configured then statistics relating to these connections can be monitored.
- **Workload** - By default, Oracle WebLogic allocates simple workload managers for each deployment. These workload managers and any custom constraints can be monitored.

Refer to the Oracle WebLogic documentation for a detailed description of each of the statistics and their relevance.

6.19 Specifying Custom Log File Names BATCH

By default the submitjob and threadpoolworker utilities will create logs in a specific location. For example:

User Exit	Platform	Default Location and Name
submitjob.sh	UNIX	\$SPLOUTPUT/submitjob.{batchCode}.{sysDateTime}.log
submitjob.cmd	Windows	%SPLOUTPUT%\submitjob.{batchCode}.{sysDateTime}.log
threadpoolworker.cmd	Windows	%SPLOUTPUT%\threadpoolworker.{sysDateTime}.log
threadpoolworker.sh	UNIX	\$SPLOUTPUT/threadpoolworker.{sysDateTime}.{pid}.log

Where:

Commands	Description
{batchCode}	Batch Control used for job
{sysDateTime}	System Date and Time in YYYYMMDDHHmmSSSS format
{pid}	Process Id

If your implementation wishes to implement custom log file names then this may be achieved using user exits which allow custom setting of the file name pattern. In the utilities an environment variable is set to the name and location of the log file. The user exit may be used to set this environment variable to an alternative. The user exit contains the script code fragment used to set the log file environment file name.

The table below lists the user exit, environment variable name and the platform:

User Exit	Platform	User Exit Name	Env Variable
submitjob.sh	UNIX	submitjob.sh.setvars.include	SBJLOGID
submitjob.cmd	Windows	submitjob.cmd.setvars.include	SBJLOGID
threadpoolworker.cmd	Windows	threadpoolworker.cmd.setvars.include	TPWLOGID
threadpoolworker.sh	UNIX	threadpoolworker.sh.setvars.include	TPWLOGID

Additionally internal session variables are available for use in the user exits:

Variable	submitjob ²⁴	threadpoolworker	Comments
RUNOPTS		■	Runtime Options
batchCode	■		Batch Code
sysDateTime	■		Run Date and Time

Note: Other environment variables in the session can be used and determined in the user exit script code.

²⁴ These are set for the Java runtime.

6.20 Turning Off L2 Cache BATCH

Note: This facility should only be used where background processes specifically require it. Turning off the cache in other circumstances will adversely affect performance.

By default, the threadpools use a batch cache to load common configuration data to avoid excessive calls to the database. In some cases it is desirable to disable the caching for a particular threadpool. To disable the cache on startup of the threadpool use the following command:

```
threadpoolworker[.sh] -l2 OFF -p <threadpoolname>
```

where <threadpoolname> is the name of the threadpool to start with the caching disabled.

Once the threadpool is started then all jobs that require caching off can be executed in this threadpool using the DIST-THD-POOL parameter (for online submission), [com.splwg.batch.submitter.distThreadPool](#) parameter in the job specific properties file or -p option on the [submitjob](#) command.

6.21 JDBC Support

Note: This facility is only available for online and web services channels only.

By default, the product uses the Universal Connection Pooling (UCP) to manage database connections. It is also possible to use Oracle WebLogic connection pooling via Data Sources for the online transactions (UCP will continue to be used for batch transactions). To use Data Sources the data sources must be created within Oracle WebLogic and then configuration files altered to utilize the Data Source using the following process:

- Create the Data Source in the Oracle WebLogic console. using the Services → Data Sources menu item. Repeat for the connection pool for online and connection pool for web services. Specify the following:

Attribute	Comment
Name	Allocate a name for monitoring and management purposes
JNDI Name	Allocate a name to be used by the connection. This is used as <datasourcename> later. It is recommended that the name be prefixed with jdbc/ to conform to naming standards.
Row Prefetch Enabled	This should be enabled.
Row Prefix Size	Specify a value between 2 - 100. Default: 48
Stream Chunk Size	This is not used by the product
Database Type	Specify Oracle
Database Driver	Specify the database driver to use. Do not use the XA versions of the driver for the product. By default use the Thin driver for Service Connections.
Supports Global Transactions	Deselect this option as it does not apply.

Attribute	Comment
One Phase Commit	Ensure this option is selected.
Database Name	Specify the Oracle SID of the database to connect to. This should correspond to DBNAME in the ENVIRON.INI.
Host Name	Specify the host allocated to Oracle. This should correspond to DBSERVER in the ENVIRON.INI.
Port	Specify the Oracle Listener Port number of the database to connect to. This should correspond to DBPORT in the ENVIRON.INI.
Database User Name	Specify the product database user. This should correspond to DBUSER in the ENVIRON.INI. If creating a separate connection pool for Web Services then it is recommended to use XAI_DBUSER in the ENVIRON.INI to separate traffic in the database.
Password	Specify the password for the user. This should correspond to DBPASS in the ENVIRON.INI. If creating a separate connection pool for Web Services then it is recommended to use XAI_DBPASS in the ENVIRON.INI to separate traffic in the database.
Initial Capacity	This is the initial size of the connection pool
Maximum Capacity	This is the maximum size of the connection pool
Capacity Increment	This is the number of connections that are added to the connection pool when necessary.
Statement Cache Type	This denotes the type of cache to use. Use the LRU setting.
Statement Cache Size	This is the cache size.

- Specify the following values in the ENVIRON.INI using the configureEnv utility:

Setting	Recommendation
<u>IWS JDBC DataSource Name</u>	Fully qualified JNDI Name for Web Services Data Source
<u>Web JDBC DataSource Name</u>	Fully qualified JNDI Name for Web Data Source

- Save the file and execute the initialSetup utility to reflect the change.
- If using native mode, redeploy the product EAR files.

6.22 Cancelling Batch Processes Using JMX **BATCH**

While JMX can be used to obtain monitoring information it is possible to cancel threads of batch processes using the operations component of JMX. To cancel a thread the following process must be performed:

- Start the JMX console of your choice and connect to the relevant JMX port configured for the batch.
- Select the thread and batch process to be cancelled from the JMX console.
- Select the Cancel operation from the operations component of the console. The console may recognize the operations of the JMX classes and allow the actions to be processed. For example, jconsole will generate cancelThread button. Issue the action.



Figure 47: CancelThread Example

Note: Depending on the JMX console used, a confirmation dialog may NOT be displayed and cannot be undone once issued. Ensure that the correct thread for the batch process is selected. To cancel a batch process, ALL threads must be cancelled.

The batch process will be marked as cancelled and stopped. The IP address of the requestor is logged in the Batch Run Tree for auditing purposes.

7. Operations from Oracle Enterprise Manager

Note:

This section of the Server Administration Guide provides an overview of using Oracle Enterprise Manager along with the Application Management Pack for Oracle Utilities to administer the product. This section assumes that Oracle Enterprise Manager and the Application Management Pack for Oracle Utilities are installed prior to using this section. If this is not the case, refer to the installation documentation for these products to complete that prerequisite installation.

7.1 Discovering Oracle Utilities Targets

Prior to using Oracle Enterprise Manager the Oracle Utilities targets must be discovered and registered with the Oracle Management Repository (OMR) within an Oracle Management Server (OMS) using Oracle Management Agents (OMA).

To discover the Oracle Utilities targets the following process must be followed:

- Install the Oracle Management Server and Oracle Management Repository to the relevant centralized server as per the Oracle Enterprise Manager documentation.

Note: It is not recommended to install the Oracle Management Server or Oracle Management Repository on the same servers housing the products.

- Deploy the Oracle Management Agents to the hosts housing the products.
- Discover and register the hosts and agents to the Oracle Management Repository using any of the methods described in the Oracle Enterprise Manager documentation.
- Start the products using the console or scripts.

Note: Oracle Enterprise Manager will only discover and register targets that are active at the time of discovery.

- Deploy the base Fusion Middleware functionality to the agents on the hosts for the products.
- Discover the Fusion Middleware targets associated with the product. This includes the domain, servers and application deployments.
- Download the Application Management Pack for Oracle Utilities via Oracle Software Delivery Cloud or Oracle Enterprise Manager Self Update.
- Deploy the Application Management Pack for Oracle Utilities to the Oracle Management Server to enable the server content.

Note: This may require a short outage on the Oracle Management Server.

- Deploy the Application Management Pack for Oracle Utilities to the Oracle Management Agents on the product hosts to enable agent content.
- Discover the Oracle Utilities Environment target using the Discovery process as documented in the Oracle Enterprise Manager documentation. All related targets will be automatically discovered.

Note: At discovery time, target names are autogenerated. They can only be renamed with more meaningful names at discovery time.

After discovery of the Oracle Utilities Environment target the following Oracle Utilities targets are discovered, registered and associated with the Oracle Utilities Environment target:

- **Oracle Utilities Web Application Target** - One or more Web Application Server targets (SPLWeb) associated with the Oracle Utilities Environment target. This target is associated with the Fusion Middleware Web Application Server base target.
- **Oracle Utilities Web Services Target** - One or more Business Application Server targets (SPLService) associated with the Oracle Utilities Environment target. This target is associated with the Fusion Middleware Web Application Server base target.
- **Oracle Utilities Home Target** - One or more software installations associated with the product associated with the Oracle Utilities Environment target.
- **Oracle Utilities Batch Server Target** - One or more Coherence hosts associated with the Oracle Utilities Environment target.


7.2 Discovering Oracle WebLogic Targets

Oracle Enterprise Manager can discover and manage the products using the Oracle Application Management Pack for Oracle Utilities.

It is possible to manage and monitor the database and Oracle WebLogic from Oracle Enterprise Manager. When using native mode, Oracle Enterprise Manager will autodiscover the Oracle WebLogic instance using its native facilities. To use Oracle Enterprise Manager with environments using the default embedded support of Oracle WebLogic the following can be used to discover and monitor the instance:

- Within Oracle Enterprise Manager console, navigate to the Add Targets Manually menu option under the Setup menu.
- Select Add Non-host Targets using Guided Process from the options list.
- Select Oracle Fusion Middleware to denote that Oracle WebLogic will be discovered.
- In the dialog specify the following values:
 - Administration Server Host - The host name used for WL_HOST in your environment. This host must be registered to Oracle Enterprise Manager as a target so that the agent is redeployed.
 - Port - The port number assigned to the environment (WL_PORT).
 - Username - An account authorized to the Oracle WebLogic console. The Oracle Utilities Application Framework installer creates an initial user system that can be used if you have not got a site specific value for this user. This userID is used, by default, for all operations to the target. It must be an Administration account not a product account.
 - Password - The password configured for the Username.
 - Unique Domain Identifier - An unique identifier for the domain to denote within Oracle Enterprise Manager. This is important and should be some value that means something for your administrator to understand. This also allows multiple targets per host to be defined easily. Make sure you do not use any embedded blanks and special characters for the name.

- Agent - This is the default host and port for the OEM agent on that machine. Just for references and can be altered if the default port is different for OEM at your site.
- Choose to Continue and the above target will be registered for use within Oracle Enterprise Manager.
- Each server in your domain will be registered as an Oracle WebLogic Server and every component of the product will be registered as an Application Deployment. For example:



Target Name	Target Type	Target Status	Line of Bus
/BTMFarm_btm_domain/btm_domain	Oracle WebLogic Domain	n/a	Business
/BTMFarm_btm_domain/btm_domain/AdminServer	Oracle WebLogic Server	Up	Business
/BTMFarm_btm_domain/btm_domain/AdminServer/FMW Welcome Page Application(11.1.0.0.0)	Application Deployment	Up	Business
/BTMFarm_btm_domain/btm_domain/btmMainServer	Oracle WebLogic Server	Up	Business
/Farm_domain/_domain	Oracle WebLogic Domain	n/a	Oracle U
/Farm_domain/_domain/jvmpool	Java Virtual Machine Pool	n/a	Oracle U
/Farm_domain/_domain/_domain/Acsra	Domain Application Deployment	n/a	Oracle U
/Farm_domain/_domain/_domain/AdminServer	Oracle WebLogic Server	Up	Oracle U
/Farm_domain/_domain/_domain/HttpDeployer	Application Deployment	Up	Oracle U
/Farm_domain/_domain/_domain/HttpDeployer	Domain Application Deployment	n/a	Oracle U
/Farm_domain/_domain/_domain/javadiagnosticagent	Domain Application Deployment	n/a	Oracle U
/Farm_domain/_domain/_domain/jmsserver1	Oracle WebLogic Server	Up	Oracle U
/Farm_domain/_domain/_domain/jmsserver1_jvm	Java Virtual Machine	Up	Oracle U
/Farm_domain/_domain/_domain/jmsserver1_Acsra	Application Deployment	Up	Oracle U
/Farm_domain/_domain/_domain/jmsserver1_javadiagnosticagent	Application Deployment	Up	Oracle U
/Farm_domain/_domain/_domain/myserver	Oracle WebLogic Server	Up	Oracle U
/Farm_domain/_domain/_domain/myserver_jvm	Java Virtual Machine	Up	Oracle U
/Farm_domain/_domain/_domain/myserver_Acsra	Application Deployment	Up	Oracle U
/Farm_domain/_domain/_domain/myserver_javadiagnosticagent	Application Deployment	Up	Oracle U
/Farm_domain/_domain/_domain/myserver_SPLService	Application Deployment	Up	Oracle U
/Farm_domain/_domain/_domain/myserver_SPLWeb	Application Deployment	Up	Oracle U
/Farm_domain/_domain/_domain/myserver_Webservices	Application Deployment	Up	Oracle U
/Farm_domain/_domain/_domain/SPLService	Domain Application Deployment	n/a	Oracle U
/Farm_domain/_domain/_domain/SPLWeb	Domain Application Deployment	n/a	Oracle U
/Farm_domain/_domain/_domain/Webservices	Domain Application Deployment	n/a	Oracle U
/EMGC_GCDomain/GCDomain	Oracle WebLogic Domain	n/a	Enterprise

Figure 48: Oracle WebLogic Targets

7.3 Oracle Utilities Targets

The following targets are available for the product:

Target	Usage
Oracle Utilities System Environment	Environment Target as a collection of other targets
Oracle Utilities Home	Software installation(s) for environment. Used to cloning and patching
Oracle Utilities Web Application	Online Web Application(s)
Oracle Utilities Web Services Application	Business Application Server Application(s)
Oracle Utilities Batch Server	Threadpool/Submitter Batch Server(s)

Refer to the [Oracle Application Management Pack for Oracle Utilities Overview](#) (Doc ID: [1474435.1](#)) for more information.

7.4 Monitoring Using Oracle Enterprise Manager

The following target types within Oracle Enterprise Manager can be used with the product directly:

Target	Monitoring Capabilities
Oracle Utilities Web Application	Availability for online transaction including Oracle WebLogic basic metrics.
Oracle Utilities Web Services Application	Online performance monitoring
Oracle Utilities Batch Server	Batch performance monitoring
Oracle WebLogic Server	Availability, JMS, MDB and URL performance information
Application Deployment	Individual deployment metrics for Online, Business Application Server and Inbound Web Services including availability, performance and other metrics.
Java Virtual Machine	JVM Diagnostics (if Oracle WebLogic Management Pack EE installed)
Database Instance	Database metrics including performance and availability

Note: It is not recommended to use the Oracle Coherence targets within Oracle Enterprise Manager for monitoring or managing the batch cluster.

8. Oracle Scheduler Integration

Note: It is not The Oracle Scheduler interface is an optional installation for using the Oracle Scheduler in the Oracle Database to schedule and execute product jobs. Customers using alternative methods or tools can ignore this section.

8.1 Introduction

The product now includes an optional interface to the Oracle Scheduler which is part of the Oracle Database. This interface allows the execution of product batch processes using the scheduling capabilities of the Oracle Scheduler.

8.2 Background Materials

Before reading this section is it recommended to familiarize yourself with the Oracle Scheduler by reading the following documentation:

- [Oracle Scheduler Concepts](#) - Overview of the scheduler including the architecture.
- [Scheduling Jobs with Oracle Scheduler](#) - Creating, running and monitoring jobs, chains and prioritization.
- [Administrating Oracle Scheduler](#) - Configuration, monitoring, import/export schedules, troubleshooting etc
- [Using Oracle Scheduler with a CDB](#) - Using Oracle Scheduler in and/or with a multi-tenant container database.
- [DBMS_SCHEDULER Reference](#) - Reference API for the Oracle Scheduler including all the valid procedures available.

Note: The Oracle Scheduler in Oracle Database 12c and above is recommended to be used for this interface.

8.3 Oracle Scheduler Interface Overview

The product now includes a PL/SQL based interface to allow Oracle Scheduler to schedule and execute product batch processes. The components of this interface are as follows:

- A set of tables to configure and control the interface. These tables are not managed by any object within the product itself as they are exclusively reserved for internal use by the Scheduler interface. These are installed in the product schema.
- A PL/SQL procedure (OUAF_BATCH) that implements an interface to Oracle Scheduler to populate the scheduler interface tables, execute jobs and manage jobs from the PL/SQL interface supported by the Oracle Scheduler. This is installed on the product schema.
- The scheduler object may exist on the same database as the product or remotely on a scheduler database. If the remote option is used then the Oracle Scheduler Agent must be installed and enabled on the product database servers. A [destination](#) and [credentials](#) must also be configured.

If [File Watchers](#) are used on product software hosts, then the [Oracle Scheduler Agent](#)²⁵ must be enabled to access the files on the hosts holding the file.

- No user interface components are supplied with the interface from the product itself. The Oracle Scheduler uses Oracle SQL Developer or Oracle Enterprise Manager to maintain, execute and monitor Oracle Scheduler objects. It is recommended customers and partners use those interfaces to manage your schedule and related objects for Oracle Scheduler.
- For the Oracle Scheduler Interface to operate at least one threadpool.
- The Oracle Scheduler interface must be installed on the product schema but the schedule can be maintained locally or remotely. To support remote invocations, it is highly recommended to setup a dedicated database user for the schedule which is independent of the product database users. The product installation guide uses the default SCHADM for this role. All schedule information is stored in this schema not the product schema.

Note: This manual will use the default value for this schedule administrator SCHADM but the actual implementation may vary.

8.3.1 Oracle Scheduler Configuration

The Oracle Scheduler interface is installed on the product database and optionally on the scheduler database (for enterprise wide deployments).

After the Oracle Scheduler interface is installed the scheduler interface operates on the following principles:

- The Oracle database holding the schedule must have the JOB_QUEUE_PROCESSES²⁶ set to the maximum number of total concurrent threads expected to execute at peak times to ensure maximum thread usage.
- The Oracle Scheduler and interface are configured to define the preferences to set the behavior:
 - The Oracle Scheduler preferences are configured with global scheduling defaults including email servers, time zones etc. For more information on the Oracle Scheduler preferences refer to [Setting Scheduler Preferences](#) and [Oracle Scheduler Preferences](#).
 - The Oracle Scheduler Interface options are set appropriately. For more information refer to Scheduler Interface Options.
- The Oracle Scheduler is configured with the following minimal schedule objects. Additional objects can be configured as outlined in [Scheduling Jobs with Oracle Scheduler](#) and Using Additional objects in Oracle Scheduler.
 - Job - Define one or more jobs per Batch Control using the Submit_Job interface. Refer to [Defining Jobs](#) for additional advice.
 - Chain - Define the dependency chain with all the jobs that need to be executed with that chain. Refer to [Defining Chains](#) for additional advice.
- Optionally, populate the parameters of the each job as outlined in Specifying Job Parameters)

²⁵ The Oracle Scheduler Agent is an option on the database installation or the Oracle Client installation.

²⁶ The default is set to 1000 jobs, unless altered.

8.3.2 Oracle Scheduler Execution

Note:

The threadpools used by any process must be started before any job can execute.

Refer to the [Scheduler Architecture](#) of how the Oracle Scheduler internally operates.

Once the scheduler objects are defined the Oracle Scheduler will initiate the batch jobs using the following technique:

- When a job in the Scheduler is deemed ready to execute, the Oracle Scheduler Interface determines the parameters from the various objects (including from the PL/SQL command line) and creates entries in the batch instance tables.
- The product batch daemon detects a pending process and distributes the job to the threadpool(s) indicated on the job parameters for execution. The Oracle Scheduler does not distribute the jobs to the threadpools, that is done via the daemon.
- During execution the monitoring capabilities in Oracle Scheduler, Oracle Enterprise Manager, JMX or the Batch Run Tree can be used to monitor the process. Refer to [Monitoring Oracle Scheduler](#) for more information.
- If the batch process fails the interface set the job to the FAILED state for the Oracle Scheduler to react accordingly. If the batch process completes successfully the interface will set the job to the SUCCEEDED state for the Oracle Scheduler to react accordingly

The following figure summarizes the flow and processing for the Oracle Scheduler, the Oracle Scheduler Interface and batch architecture:




Figure 49: Oracle Scheduler Interface

8.4 Oracle Scheduler Interface (OUAF_BATCH)

The Oracle Scheduler Interface is a PL/SQL based package OUAF_BATCH which contains a number of procedures to initiate batch processes, cancel running batch processes and manage the parameters for the interface.

8.4.1 Submit_Job - Submit a Job or Thread

The `Submit_Job` procedure submits a batch job and waits for it to complete or fail. It returns `COMPLETED` or `FAILED` state to the Oracle Scheduler when used in a Job or Program object.

Column Name	Data Type	Requirement	Description
batch_code	Text	■	Valid batch control
user_id	Text	■	Valid product user defined in user object. The email address specified on the user object is used to send any configured notifications. Value can be inherited from configured parameters.
thread_count	Number		Override for thread count on batch control.
business_date	Date		Process date to be used for batch job. Value can be inherited from configured parameters. Value can be set using the to_date function. If no value is provided, the current date will be used. The format of the date must be in a recognizable format. For example, DD-MMM-YYYY is supported. It is recommended to use the to_date function to avoid confusion.
max_timeout_mins	Number		Maximum timeout, in minutes, for transactions to avoid ORA-01555 Snapshot too old errors . Default is 15.
rerun_number	Number		Used for rerunning specific extracts. Default is: 0 (zero) for current extract.
thread_pool	Text		Valid Threadpool name to execute this batch job. This corresponds to the DIST-THD-POOL parameter. If not provided at all, the value of DEFAULT is assumed.
min_run_status	Number		Minimum Run Status that will cause this procedure to exit. The default is <code>RUN_STAT_COMPLETED</code> (40). Other values supported: <ul style="list-style-type: none"> • 10 - <code>RUN_STAT_PENDING</code> • 20 - <code>RUN_STAT_IN_PROGRESS</code> • 30 - <code>RUN_STAT_ERROR</code> • 40 - <code>RUN_STAT_COMPLETED</code>

Column Name	Data Type	Requirement	Description
raise_error	Boolean		If the min_run_status is set a value less than 40, this parameter is set to true and the job status matches the value of the min_run_status then raise an application error. This allows the chain to support conditional branches or stop chains on conditions. Default is false.
thread_notifications	Boolean		Whether if an error in any thread should trigger a notification event. Default is true. See Notification Options for more information.
soft_parm_map	Array		Associate array of soft parameters. Refer to Specifying Job Parameters for more details.
soft_parm_list	Array		Table array of soft parameters. Refer to Specifying Job Parameters for more details.

Example command lines:

```

begin
    OUAF_BATCH.Submit_Job(
        batch_code => 'F1-SYNRQ',
        user_id => 'FRED01',
        thread_count => 4,
        business_date => '01-JUN-15',
        max_timeout_mins => 15,
        rerun_number => 0,
        thread_pool => 'DEFAULT',
        min_run_status => OUAF_BATCH.RUN_STAT_COMPLETED,
        raise_error => true,
        thread_notifications => true,
        soft_parm_list
            => OUAF_BATCH.parm_list_t('someParm', 'someValue'));
end;
begin
    OUAF_BATCH.Submit_Job(batch_code => 'F1-SYNRQ', user_id =>
'FRED01');

```

```
end;
begin
    OUAF_BATCH.Submit_Job(batch_code => 'F1-SYNRQ',
                          user_id => 'FRED01',
                          business_date => to_date('2016-01-01','YYYY-
MM-DD'),
                          thread_count => 1);
end;
begin
    OUAF_BATCH.Submit_Job(batch_code => 'F1-SYNRQ',
                          user_id => 'FRED01',
                          thread_pool => 'POOL01');
end;
begin
    OUAF_BATCH.Submit_Job(
        batch_code => 'F1-SYNRQ',
        user_id => 'FRED01',
        soft_parm_list =>
        OUAF_BATCH.parm_list_t('maintenanceObject','F1-SYNC REQ',
                               'isRestrictedByBatchCode','true'));
end;
begin
    OUAF_BATCH.Submit_Job(batch_code => 'F1-SYNRQ',
                          user_id => 'FRED01',
                          business_date => to_date('2015-06-01','YYYY-
MM-DD'));
end;
```

8.4.2 Restart_Thread - Restart a Failed Thread/Job

If a batch job or a thread of a job has failed and needs to be restarted the OUAF_BATCH includes an operation to restart the thread.

The Restart_Thread procedure uses the same parameters of the Submit_Job procedure with an additional parameter:

Column Name	Data Type	Requirement	Description
thread_number	Number	■	Thread Number to restart. For single threaded jobs, this should be set to 1.

The parameters can match the original execution or be altered to change the behavior of the individual thread.

Note: The thread_count should match the original to ensure all data is processed correctly.

The major difference between Submit_Job procedure and Restart_Thread procedure is that Restart_Thread procedure does not wait for the thread to complete. It simply ends after submitting the thread. Therefore it is not recommended to be used in a schedule in Oracle Scheduler.

Examples of the command are as follows:

```
begin
    OUAF_BATCH.Restart_Thread(batch_code => 'F1-SYNRQ',
                               thread_number => 2,
                               user_id => 'FRED01',
                               thread_count => 4,
                               business_date => '01-JUN-15',
                               max_timeout_mins => 15,
                               rerun_number => 0,
                               thread_pool => 'POOL01');
end;
```

8.4.3 Cancel_Job - Cancel a Running Job

Note:

This technique is an alternative to the technique outlined in [Batch JMX Reference](#).

The dbms_scheduler.[stop_job](#) procedure is recommended to stop a scheduler job.

A job that is executing can be stopped using the Cancel_Job procedure. The procedure can use one of the following identifiers to cancel the running job.

Column Name	Data Type	Description
batch_code	Text	Valid batch control

Column Name	Data Type	Description
job_id	Number	Allocated job identifier from batch daemon (on ci_batch_job table).

For example:

Begin

```
OUAF_BATCH.Cancel_Job(job_id => '00000000000123',
                      batch_code => 'F1-SYNRQ');
```

end;

Begin

```
OUAF_BATCH.Cancel_Job(job_id => '00000000000123');
```

end;

begin

```
OUAF_BATCH.Cancel_Job(batch_code => 'F1-SYNRQ');
```

end;

The Cancel_Job procedure asynchronously changes the running Submit_Job status to CANCELLED state and terminates. The Submit_Job instance continually monitors the status and will take appropriate action to cancel all the running threads and end with a cancellation error once all the threads have ended.

Refer to [Cancellation](#) for more details.

8.4.4 Set_Option - Set a Global or Job Option

The Set_Option procedure is used to set global or job specific options for the scheduler interface. Any option specified using this procedure is subject to the Order Of Preference for parameters.

The Set_Option procedure uses the following command format:

begin

```
OUAF_BATCH.Set_Option(scope => '<scope>', name => '<parmname>',
                      value => '<parmvalue>');
```

end;

Command	Description
<scope>	Scope of the parameter. The valid values are GLOBAL for global settings or a valid Batch Control for a specific Batch Control. Settings at the Batch Control level override the GLOBAL scope.
<parmname>	The parameter name from the list below. This setting can be overridden on the command line.
<parmvalue>	The value of the parameter designated by <parmname> to be used for the scope designated by <scope>.

The parameters supported by this option are listed below:

Parameter Name	Description
business_date	The default business date is the database's current system date, but this can provide an alternative default. It is typically useful in the case of jobs that run past midnight to make it maintain the same date for all the submissions. The date format is ISO format: YYYY-MM-DD.
user_id	The User ID is required for every submission but to avoid having to specify it on every Submit_Job call, this will define a default either globally or for specific batch codes. The user must be defined as an user object within the product.
poll_seconds	By default the batch tables are checked every 1 second for updates. This provides for very responsive job handling, but if it is too taxing on the database, the frequency can be modified with this setting. The value must be between 1 and 60.
notify_job_name	Oracle Scheduler job OUAF_NOTIFY is the default thread notification job. That is defined out of the box to send emails for every failed thread. If that behavior is undesired, a custom thread notification, Oracle Scheduler job can be created and it defined as the default handler with this option. The new notify Oracle Scheduler job must exist.
thread_notifications	Set to false to suppress thread notifications for failed threads. The default is true.
thread_pool	The default threadpool to use. The installation default threadpool is 'DEFAULT'.
discard_queue	Set to true to delete all unused online job queue entries (CI_BATCH_JOB rows) created by OUAF_BATCH. The default is false. OUAF_BATCH uses individual CI_BATCH_JOB rows for the threads so it may become quite voluminous, and the job queue entries are typically not useful once a thread has started executing as the Batch Run Tree entries are used to track the job. This option can be used to clean up the unused entries.
debug	Set to true to see internally generated DBMS_OUTPUT debug messages. The default is false. Used for development purposes.

For example:

Begin

```
    OUAF_BATCH.Set_Option(scope => 'GLOBAL', name => 'user_id', value
=> 'FRED01');
```

end

To remove the option, use the [Unset_Option](#) procedure.

8.4.5 **Unset_Option** - Reset a Global or Job Option

By using the **Set_Option** feature sets the global or job specific parameters for the scheduler it is possible to also remove the settings using the **Unset_Option** feature on the parameters covered by the **Set_Option** feature. The format of the command is:

```
begin
    OUAF_BATCH.Unset_Option(scope => '<scope>', name => '<parmname>');
end;
```

Command	Description
<scope>	Scope of the parameter to reset. The valid values are GLOBAL for global settings or a valid Batch Control for a specific Batch Control.
<parmname>	The parameter name to reset. Refer to the Set_Option procedure for the valid list.

For example:

```
begin
    OUAF_BATCH.Unset_Option(scope      => 'GLOBAL',
    'business_date');
end;
```

8.4.6 **Raise_Thread_Error** - Raise an Error

Whenever a thread or job fails the Oracle Scheduler Interface informs the product of the failure as well as the scheduler itself. This is handled by the **Raise_Thread_Error**. This procedure is not directly called by the scheduler itself and is used internally by the interface itself.

8.4.7 **Setting Preferences**

One of the first steps in configuration is setting the preferences

- The Oracle Scheduler includes a number of key preferences that need to be configured to ensure a consistent operation of the scheduler. These preferences are documented in the [Setting Scheduler Preferences](#) section of the [Oracle Scheduler Administration](#) documentation. It is recommended to set the preferences before using any of the functionality in the Oracle Scheduler.
- Once the Oracle Scheduler Interface is installed the GLOBAL options for the interface, should be set if they differ from the recommended defaults. This can be achieved using the [Set_Option](#) procedure. At a minimum, it is recommended to set a global user_id to act as a default to avoid individual job issues.
- Optionally, it is possible to set Batch Job specific options using the Batch Control as the key for the [Set_Option](#) procedure.

The above facilities set the overall scheduler and interface preferences.

8.4.8 Order of Preference

There are a number of different techniques available for setting the parameters for any job. The available techniques from lowest precedence to highest are as follows:

- **Batch Control** - Job parameters can be set on the Batch Control record within the user interface under control of authorized users. This is commonly maintained by the business.
- **Global Preferences** - Some of the parameters from the Batch Control can be specified as a GLOBAL preference using the [Set Option](#) procedure. These preferences, if set, will override any Batch Control settings for the same setting.
- **Batch Job Preferences** - The [Set Option](#) procedure also supports the setting of parameters using the Batch Control as the key. Any overlapping settings set at this level will override settings on the Batch Control and any GLOBAL preference for the same setting.
- **Command Line Options** - It is possible to override all settings using command line options on the [Submit Job](#) and [Restart Thread](#) procedures. This is handy for special processing. See [soft_parm_map](#) and [soft_parm_list](#) for advice and examples.

It is recommended to set the values in the relevant level and use command line options for special situations or when using dynamic parameters.

8.4.9 Using [soft_parm_map](#)

Batch parameters can be specified on the command line through the [soft_parm_map](#), which is an [associative array](#). This format can be used in isolation or in association with [soft_parm_list](#) when specifying command line parameters. When both are used, the [soft_parm_list](#) values are taken in precedence

To use [associative arrays](#), the array must be declared before use in the PL/SQL command.

Any array must be declared as type `OUAF_BATCH.parm_map_t`.

The format of soft parameter in an [associative array](#) is:

Segment	Format
Declaration of array	<code>declare <arrayname> OUAF_BATCH.parm_map_t;</code>
Definition of value	<code><arrayname>('<parmname>') := '<parmvalue>';</code>
Use of map	<code>soft_parm_map => <arrayname></code>

Where:

Parameter	Description
<code><arrayname></code>	Name of associative array to be used as the <code>soft_parm_map</code>
<code><parmname></code>	Name of the parameter to be set
<code><parmvalue></code>	Value of parameter

For example:

```

declare
  my_soft_parms  OUAF_BATCH.parm_map_t;
begin
  my_soft_parms('maintenanceObject') := 'F1-SYNC REQ';
  my_soft_parms('isRestrictedByBatchCode') := 'true';
  OUAF_BATCH.Submit_Job(batch_code => 'F1-SYNRQ',
                        user_id => 'FRED01',
                        soft_parm_map => my_soft_parms);
end;

```

The my_soft_parms is the soft_parm_map in the above example. The use of associative arrays is a way of supporting dynamic parameters for complex parameters. This technique can be used exclusively or in conjunction with [soft_parm_list](#).

Note: The associative array should not contain common parameters such as business_date, user_id etc.

8.4.10 Using soft_parm_list

An alternative to the soft_parm_map is to explicitly specify the parameters as a list of parameter and value pairs. This method is recommended for explicit values for the parameters. The parameter list must be of type OUAF_BATCH.parm_list_t.

The parameters are specified in the following format:

OUAF_BATCH.parm_list_t('<parmname>','<parmvalue>'...)

Where:

Parameter	Description
<parmname>	Name of the parameter to be set
<parmvalue>	Value of parameter

For example:

```

begin
  OUAF_BATCH.Submit_Job(
    batch_code => 'F1-SYNRQ',
    user_id => 'SYSUSER',
    soft_parm_list =>
      OUAF_BATCH.parm_list_t('maintenanceObject', 'F1-SYNC
REQ',
      'isRestrictedByBatchCode', 'true'));
end;

```

This technique can be used exclusively or in conjunction with [soft_parm_map](#).

Note: The array should not contain common parameters such as business_date, user_id etc.

8.5 Building a Schedule

Note: This section summarizes the features of the scheduling jobs in Oracle Scheduler using the Oracle Scheduler integration. Refer to [Scheduling Jobs with Oracle Scheduler](#) for additional information.

To use the Oracle Scheduler the scheduler objects must be loaded and the command lines use the provided Oracle Scheduler Interface PL/SQL package.

8.5.1 Recommended Tools

There are a number of tools that are recommended to be used to define, maintain and manage the Oracle Scheduler:

- PL/SQL interface - There is a PL/SQL based command line interface that can be used to define the scheduler objects and control the scheduler via the DBMS_SCHEDULER package from any SQL interface tool. For more information about the PL/SQL interface, refer to the [DBMS_SCHEDULER Reference](#). This is useful for direct access environments. It is also used by the other tools, via generated statements, to manage the Oracle Scheduler.
- Oracle SQL Developer - Oracle SQL Developer includes an interface to manage scheduler objects including wizards to define key objects. For example:




Figure 50: Example Oracle SQL Developer Oracle Scheduler Interface

- Oracle Enterprise Manager - The database targets associated with the Oracle Scheduler allow for the definition, management and monitoring scheduler objects. For example:




Figure 51: Example Oracle Enterprise Manager Oracle Scheduler Interface

It is possible to use any of the interfaces above to manage your schedule objects. Refer to the help pages associated with each tool for additional advice on individual objects.

8.5.2 Defining Programs

Note: Definition of Program Objects is optional and can be replaced directly with Job definitions. It is recommended that Program Objects be used for maximum reuse.

The first step in the process is to define each batch control as a Program object in the scheduler using the following attributes:

Attribute	Recommended Content
program_name	Name of the Program. This name should not include any embedded characters or '-' character according to Oracle object naming conventions.
comments	A short description of the program. This is useful for searching the program.
enabled	Set to true to enable this program to be used by the scheduler.
program_type	Specify the PL/SQL Block as the type of program for the Oracle Scheduler Interface.
program_action	<p>Specify the interface commands line for the execution. You may include any overrides, if desired, at this time. For optimization purpose, only specify the parameters that are not inherited from the global options or are not defaulted on the batch control.</p> <p>It is recommended to specify the Batch Control to avoid issues in submission.</p> <p>An example of a simple command line is:</p> <pre>begin OUAF_BATCH.Submit_Job(batch_code => 'BATCH01'); end;</pre>

There are number of ways that can be used to specify the program using the various tools available:

Interface	Method of Definition
PL/SQL	Use the DBMS_SCHEDULER.CREATE_PROGRAM procedure using the above parameters to define the program object.
SQL Developer	Use the New Program menu item of the Scheduler tree to define the new program using a right click action on the Program node.
Enterprise Manager	Using the Administration → Oracle Scheduler → Programs menu item, specify the program information as above. Use the Source field to hold the PL/SQL command line for the interface.

You may create more than one program for the same batch control if there are different parameters is needed for different executions.

8.5.3 Defining Job Classes

Note:

The use of Job Classes is optional. It is only used to group jobs for attribute inheritance, service affinity, monitoring purposes and/or resource profiling. DEFAULT_JOB_CLASS is used if no job class is specified. Job Class is only one technique for prioritizing jobs. Refer to [Prioritizing Jobs](#) for more information.

If [Job Classes](#) are to be used, they need to be setup to be used by the jobs allocated to them. This attributes of a Job Class are as follows:

Attribute	Recommended content
job_class_name	Name of the Job Class. This name should not include any embedded characters or '-' character according to Oracle object naming conventions.
comments	A short description of the job class. This is useful for searching for the job class.
resource_consumer_name	Name of the resource consumer group associated with jobs in this job class. Optional.
service	Name of database service associated with this job class name. Optional.
logging_level	Sets the level of logging is performed by the Oracle Scheduler. Optional.
log_history	Sets the retention period, in days, log history are retained by the Oracle Scheduler. Optional.

There are number of ways that can be used to specify the program using the various tools available:

Interface	Method of Definition
PL/SQL	Use the DBMS_SCHEDULER.CREATE_JOB_CLASS procedure using the above parameters to define the job class object.
SQL Developer	Use the New Job Class menu item of the Scheduler tree to define the new job class using a right click action on the Scheduler node.
Enterprise Manager	Using the Administration → Oracle Scheduler → Job Class menu item, specify the class information as above.

8.5.4 Defining Schedules

Note:

This section is only a subset of the capabilities of the schedule object. For more advanced discussions and different scenarios refer to the Creating and Managing Schedules to Define Jobs in the Oracle Database documentation.

Before defining jobs and chains you may need to define a schedule to run them against. Schedules can be time based and/or event based. It is also possible to create multiple schedules to support complex scheduling requirements. For example, you can create a holiday schedule with the dates that are blacklisted for execution in another schedule.

The following attributes are typically populated for the schedule object:

Attribute	Recommended content
schedule_name	Name of the schedule. This name should not include any embedded characters or '-' character according to Oracle object naming conventions.
comments	A short description of the schedule. This is useful for searching the schedule.
start_date	Optional start date and time when the schedule becomes valid. If not populated then the date jobs or windows are activated is used.
repeat_interval	This specifies how often the schedule repeats. It uses the Calendaring Syntax supported by the Oracle Scheduler. Even schedules decide the repeat interval for checking the event.
end_date	Optional date and time after jobs and windows allocated to this schedule will not execute.

There are number of ways that can be used to specify the schedule using the various tools available:

Interface	Method of Definition
PL/SQL	Use the DBMS_SCHEDULER.CREATE_SCHEDULE procedure using the above parameters to define the schedule object. This interface is recommended for complex Calendaring Syntax support.
SQL Developer	Use the New Credential menu item of the Scheduler tree to define the new schedule using a right click action on the Schedule node.
Enterprise Manager	Using the Administration → Oracle Scheduler → Schedules menu item, specify the schedule information as above.

8.5.5 Defining Remote Destinations and Credentials

Note:

This section outlines the process of specifying destinations and credentials for remote processing. If the database scheduler is housed within the product database (the default installation) then this section only applies to File Watcher type jobs.

In Oracle Database 12c, the `CREATE_CREDENTIAL` procedure for `DBMS_SCHEDULER` has been deprecated and replaced with the [CREATE_CREDENTIAL](#) procedure within the [DBMS_CREDENTIAL](#) package.

When executing Jobs and File Watchers that are remote from the scheduler database and location, it is required that a destination be defined for the job and relevant credentials for the job to execute on that destination. The following needs to be setup:

- To execute product jobs remotely, the product database server needs to be defined as a destination and the product database credentials should be specified. It is recommended that the values expressed in `BATCH_DBUSER` and `BATCH_DBPASS` be specified as credentials.
- For File Watcher jobs, the product server where the file is housed must be defined as a destination. The operating system credentials for the batch process must be specified to access the file must be specified as credentials.
- There is no explicit process for creating non-database related destinations in the API (there is no `CREATE_AGENT_DESTINATION` procedure). When an agent registers with the database scheduler as part of the startup procedure, it is automatically added as a destination. If you wish to register remote databases then use the [CREATE_DATABASE_DESTINATION](#) package.
- For Database Destinations, the database TNS information must exist on the scheduler database to connect remotely.
- At least one product related database destination must be registered for remote invocation of product jobs.
- The Oracle Scheduler agents must be executing for the scheduler to initiate and track remote jobs.

To specify the credentials the following attributes must be provided:

Attribute	Recommended content
Attribute	Name of the credential. This name should not include any embedded characters or '-' character according to Oracle object naming conventions.
credential_name	This attribute is not used by the DBMS_SCHEDULER package but can be provided for documentation purposes.
comments	The userid to be used for connection. This attribute is required and is case sensitive.
username	The password associated with the username. This value is stored in obfuscated format and is not available in Oracle Scheduler views.
password	This is the database role associated with this user. This is not used for product jobs but is required for any DBA tasks requiring privilege access.
database_role	For Windows Server implementations only. This is the windows domain for the user to connect to.
windows_domain	Name of the credential. This name should not include any embedded characters or '-' character according to Oracle object naming conventions.

There are number of ways that can be used to specify the credentials using the various tools available:

Interface	Method of Definition
PL/SQL	Use the DBMS_CREDENTIAL.CREATE_CREDENTIAL procedure using the above parameters to define the credential object.
SQL Developer	Use the New Credential menu item of the Scheduler tree to define the new credential using a right click action on the Credentials node. Oracle SQL Developer uses DBMS_CREDENTIAL for credential management.
Enterprise Manager	Oracle Enterprise Manager uses its own security system for credentials. Refer to the Enterprise Manager Cloud Control Security Guide for more details.

When specifying Database Destinations, the following attributes need to be specified:

Attribute	Recommended content
destination_name	Name of the destination. This name should not include any embedded characters or '-' character according to Oracle object naming conventions.
comments	This attribute is not used by the DBMS_SCHEDULER package but can be provided for documentation purposes.
agent	The agent name as specified in the agent configuration file.
tns_name	Oracle service name as documented in the TNS file attached to the configuration file. This is used to connect from the scheduler database to the remote database.

There are number of ways that can be used to specify the database destination using the various tools available:

Interface	Method of Definition
PL/SQL	Use the DBMS_CREDENTIAL.CREATE_DATABASE_DESTINATION procedure using the above parameters to define the credential object.
SQL Developer	Use the New Database Destination menu item of the Scheduler tree to define the new destination using a right click action on the Database Destinations node.
Enterprise Manager	Oracle Enterprise Manager uses its own security system for destinations. Refer to the Enterprise Manager Cloud Control Security Guide for more details.

8.5.6 Defining Jobs

Note:

This section is only a subset of the capabilities of the job object. For more advanced discussions refer to the Jobs section in the Oracle Database documentation.

Product jobs should never be defined as Lightweight jobs. Those are reserved for specific Oracle products.

The key object in the Oracle Scheduler is the Job object. This object is a collection of data that tells the scheduler what, when, where and how to execute a particular process. In the case of the product, a job defines how to execute an instance of a Batch Control whether it is independent or part of a Chain.

Each Job definition has a set of attributes that define the Job:

Attribute	Recommended content
job_name	Name of the job. This name should not include any embedded characters or '-' character according to Oracle object naming conventions. It is recommended to replace '-' in Batch Controls with '_' to avoid naming issues.
comments	Description of Job. Useful for finding jobs.
job_type	If programs have been used then the type STORED_PROCEDURE should be used. If programs are not used, then specify PLSQL_BLOCK with the action containing the source PL/SQL command.
job_action	Value depends on the specification of the job_type: If job_type is STORED_PROCEDURE, then this will contain the fully qualified name of the program to execute. If job_type is PLSQL_BLOCK, then this will contain the PL/SQL command to execute the OUAF_BATCH interface
start_date	Optional start date and time when the schedule becomes valid. If not populated then the date jobs or windows are activated is used. If schedule_name is specified, then this date and time may be null to inherit the value from the schedule or chain.

Attribute	Recommended content
repeat_interval	Optional. Definition of how often the job will repeat. It uses the Calendaring Syntax supported by the Oracle Scheduler. Even schedules decide the repeat interval for checking the event. If schedule_name is specified, then this value may be null to inherit the value from the schedule or chain.
schedule_name	Optional. Name of schedule object dictating the schedule for this job.
job_class	Optional. Name of job class allocated to this job.
end_date	Optional date and time after jobs and windows allocated to this job will not execute. If schedule_name is specified, then this date and time may be null to inherit the value from the schedule or chain.
credential_name	Optional. Name of credential to use for remote invocation for this job.
destination_name	Optional. Name of destination to use for remote invocation for this job. For remote product jobs this must be the location of the product database.
enabled	Whether this job is enabled or not. Only enabled jobs (true) are executed.
auto_drop	Whether after execution of this job, the job definition will be dropped. This is typically set to true for temporary jobs only. It is recommended to set to false for all regular product jobs.

There are additional attributes to manage the advanced features of the job. Refer to the Job Object for a discussion of the additional parameters.

There are number of ways that can be used to specify jobs using the various tools available:

Interface	Method of Definition
PL/SQL	Use the DBMS_SCHEDULER.CREATE_JOB procedure using the above parameters to define the job object.
SQL Developer	Use the New Job menu item of the Scheduler tree to define the new job using a right click action on the Jobs node.
Enterprise Manager	Using the Administration \rightarrow Oracle Scheduler \rightarrow Jobs menu item, specify the job information as above.

8.5.7 Defining Chains

Note: It is recommended to review the Creating and Managing Job Chains documentation for additional advice.

Once the jobs and schedule have been defined the next step is to define the set of job chains which configure the order and rules for a sequence of related jobs. Typically a job chain represents a set of business related processes that must be scheduled and processed in a specific order. For example, a nightly set of jobs that constitute a set of business processes is considered a chain.

There are a various rules for a chain:

- There is a begin event and an end event that are automatically generated for a chain. The chain is considered ended when all jobs directly related to the end event are complete.
- Relationships in the chain are based upon job state events to dictate next actions. Typically, this is SUCCEEDED but can support other events. For example, it is possible to start the next job in a chain based upon a FAILED event to perform cleanup activities if required.

There are a number of key steps outlined in Creating and Managing Job Chains that should be performed with the following additions building chains that include product jobs:

- The naming conventions for the objects defined in the chain are subject to rules for all Oracle dictionary objects. It is recommended to prefix customizations with CM_ to avoid conflicts with base provided objects.
- It is recommended to implement a chain step per batch control that is applicable to the chain. The step name can match the Batch control or a valid alternative for your implementation.
- For each sequence in the chain, set the appropriate state in a Chain Rule for the setup. For example, if StepB must start only if StepA is complete then set the condition for the rule for Step A as "StepA SUCCEEDED" and action as "START StepB". Complex rules are supported. Refer to Adding Rules to a Chain for more details.

There are number of ways that can be used to specify chains using the various tools available:

Interface	Method of Definition
PL/SQL	Refer to Creating and Managing Job Chains for the sequence of statements to execute.
SQL Developer	Use the New Chain menu item of the Scheduler tree to define the new chain using a right click action on the Chains node.
Enterprise Manager	Using the Administration→Oracle Scheduler →Chains menu item, specify the chain information.

8.5.8 Other Scheduler Objects

There are number of scheduler objects not covered in the above documentation that can be used by implementations using the following guidelines:

- **File Watchers** - These objects create events based upon an arrival of a file in a configured location. To use File Watchers, a destination and credentials need to be defined along with the File Watcher itself. The file needs to be accessible by the process that is using it.
- **Windows** - These are definitions of times and dates where certain conditions, restrictions or resource profiles can be used. Oracle Scheduler supports discrete or overlapping Windows²⁷.

²⁷ Whilst supported, Oracle does not recommend overlapping windows.

- **Groups** - It is possible to group certain scheduler objects for efficient administration and clustering purposes.

8.6 Executing Jobs

There are a number of techniques that can be used to execute a schedule and/or a job. The following techniques can be used:

- Chains can be executed using a predefined schedule or manually started by starting the job created for the chain. Refer to Running Jobs for additional information.
- Events can trigger jobs when the event occurs. Refer to Using Events to Start Jobs for more information.

Chains and Jobs that are enabled are only executed.

8.7 Monitoring Oracle Scheduler

There are various techniques available from the interface and related tools to monitor Oracle Scheduler. Refer to Monitoring Jobs for additional advice.

Note: Any product job can also be monitored using the Batch Run Tree, JMX interface or via the Oracle Utilities Batch Server target page within Oracle Enterprise Manager via the Application Management Pack for Oracle Utilities.

8.7.1 Job States

When any job is waiting to be executed, executing, completed or errored the scheduler updates the state of the job in its job tables. These states are available from the tools mentioned earlier in various forms. The states that are raised are documented in Monitoring Job State with Events Raised by the Scheduler.

8.7.2 Dictionary Views

The most common technique for monitoring the scheduler itself is the provided Scheduler Data Dictionary Views. These views not only provide details of the Oracle Scheduler Objects but can provide execution information. There are two views that are of particular interest for executions:

- *_SCHEDULER_RUNNING_CHAINS - Show all chains that have active jobs.
- *_SCHEDULER_RUNNING_JOBS - Show state information for all jobs running at the moment.

These views are accessible from any SQL product or via Oracle Enterprise Manager via the Administration → Oracle Scheduler → Home menu item on the database target used by the Oracle Scheduler.

8.7.3 Scheduler Notifications

One of the features of the Oracle Scheduler is that it is possible to send an email based upon the state of a particular job within the scheduler. This is based upon the state of the job and the email format can be customized based upon the state. For more information and examples of the capability refer to Monitoring Job State with E-mail Notifications.

The Oracle Scheduler Interface includes the OUAF_NOTIFY job that can be used as a template.

8.8 Cancellation

Once a job has been executed there are two techniques for cancelling a running job or thread:

- Use the OUAF_BATCH.Cancel_Job API to stop the thread or job. The job state will be set to STOPPED.
- Use the Batch JMX API to cancel a thread.

The cancellation will be registered on the batch run tree including any relevant security information for auditing purposes.

8.9 Exporting Schedules Across Environments

As the schedule is a set of dictionary objects it can be exported and imported using any of the Oracle database copy, cloning or exporting functions. Utilities such as exp or expdp can be used to export the schema of the owner of the schedule.

It is also possible to isolate the scheduler objects using the data pump INCLUDE function. The INCLUDE statement should use the following filter:

```
INCLUDE=procobj:"IN (SELECT NAME FROM sys.OBJ$ WHERE TYPE# IN (47,48,66,67,68,69,71,72,74))"
```

For example:

```
expdp <user>/<password> DIRECTORY=<directory> DUMPFILE=<expfile> LOGFILE=<logfile>
SCHEMAS=<schema> INCLUDE=procobj:"IN (SELECT NAME FROM sys.OBJ$ WHERE TYPE# IN
(47,48,66,67,68,69,71,72,74))"
```

Appendix A : Parameters

A.1 Conventions Used in This Section

This section contains a number of conventions to illustrate attributes and scope of configuration parameters:

- Valid values are indicated for each parameter and where applicable the default which is indicated in bold.
- The scope of the parameter is indicated with relevant icons:

WEB	Web Application Server
BAS	Business Application Server
IWS	Inbound Web Services
XAI	XML Application Integration
DB	Database
BATCH	Background Processing
MOB	Mobile based products only

- Some parameters depend on the J2EE Web Application Server used. The following icons will be used to denote the applicable J2EE Web Application Server. No icon indicates the parameter applies across all supported J2EE Web Application Server:

WLS	Oracle WebLogic
WAS	IBM WebSphere
WASND	IBM WebSphere Network Deployment

- Some parameters apply to embedded mode installation settings for Oracle WebLogic. These do not need to be set for native mode installations. The following icons will indicate these settings:

EMBED	Embedded Mode
NATIVE	Native Mode

- The ordinality of the parameter is indicated. Parameters that are mandatory must exist and are set in the relevant configuration file for the product to operate.
- Where applicable an example is indicated with the format.

A.2 ENVIRON.INI

The ENVIRON.INI is the environment file that is output from configureEnv and is used by initialSetup to build the configuration files from templates.

A.2.1 ADDITIONAL_RUNTIME_CLASSPATH - Additional Classpath

Parameter	ADDITIONAL_RUNTIME_CLASSPATH
Description	Additional Runtime Classpath for Web Application Server to allow custom jar libraries to be added to path, for Oracle WebLogic. For native mode customers, additional jar libraries can be added on the classpath on the Server definition.
Ordinality	Optional
Valid Values	Valid Classpath
J2EE Web Application Server	WLS
Tier	WEB
Installation Mode	EMBED

A.2.2 ADDITIONAL_STOP_WEBLOGIC - Additional Stop Arguments

Parameter	ADDITIONAL_STOP_WEBLOGIC
Description	Additional Stop arguments when running the Administration Server on a different port. Refer to Starting and Stopping Servers for more information.
Ordinality	Optional
Valid Values	Valid Stop options for Oracle WebLogic
J2EE Web Application Server	WLS
Tier	WEB
Installation Mode	EMBED

A.2.3 ADF_HOME - Location of ADF Software

Parameter	ADF_HOME
Description	Location of Oracle ADF libraries. Only set if ADF Zone Type is used in implementation or within product.
Ordinality	Optional
Valid Values	Full path to ADF libraries on server
J2EE Web Application Server	WLS
Tier	WEB BAS
Installation Mode	EMBED NATIVE

A.2.4 ANT_ADDITIONAL_OPT - Additional Options for ANT

Parameter	ANT_ADDITIONAL_OPT
Description	Implementation specific options for WAR and EAR builds used by initialSetup.
Ordinality	Optional
Valid Values	Valid ANT options
J2EE Web Application Server	WLS WAS WASND
Tier	WEB BAS IWS XAI BATCH MOB
Installation Mode	EMBED NATIVE

A.2.5 ANT_HOME - Location of ANT

Parameter	ANT_HOME
Description	Generated location of ANT used by initialSetup. This value is autogenerated and should not be altered.
Ordinality	Mandatory
Valid Values	Valid location of ANT
J2EE Web Application Server	WLS WAS WASND
Tier	WEB BAS IWS XAI BATCH MOB
Installation Mode	EMBED NATIVE

A.2.6 ANT_OPT_MAX - ANT Maximum Heap Size

Parameter	ANT_OPT_MAX
Description	Maximum memory in MB allocated to ANT builds. Unless otherwise instructed by Oracle Support this value should not be altered.
Ordinality	Optional
Valid Values	Default: 800
J2EE Web Application Server	WLS WAS WASND
Tier	WEB BAS IWS XAI BATCH MOB
Installation Mode	EMBED NATIVE

A.2.7 ANT_OPT_MIN - ANT Minimum Heap Size

Parameter	ANT_OPT_MIN
Description	Minimum memory in MB allocated to ANT builds. Unless otherwise instructed by Oracle Support this value should not be altered.
Ordinality	Optional
Valid Values	Default: 200
J2EE Web Application Server	WLS WAS WASND
Tier	WEB BAS IWS XAI BATCH MOB
Installation Mode	EMBED NATIVE

A.2.8 appViewer - Name of appViewer WAR File

Parameter	appViewer
Description	Name of AppViewer WAR file
Ordinality	Mandatory
Valid Values	This value is automatically generated
J2EE Web Application Server	WLS WAS WASND
Tier	WEB
Installation Mode	EMBED NATIVE

A.2.9 BATCHDAEMON - Whether Online Batch Daemon is Enabled

Parameter	BATCHDAEMON		
Description	Whether the Online Batch Daemon is enabled or not.		
Ordinality	Mandatory		
Valid Values	[true false]		
J2EE Web Application Server	WLS	WAS	WASND
Tier	BAS	BATCH	
Installation Mode	EMBED	NATIVE	

A.2.10 BATCHEDIT_ENABLED - Whether Batch Edit Facility is Enabled

Parameter	BATCHEDIT_ENABLED		
Description	Whether the Batch Edit facility is enabled or not.		
Ordinality	Mandatory		
Valid Values	[true false]		
J2EE Web Application Server	Not Applicable		
Tier	BATCH		
Installation Mode	Not Applicable		

A.2.11 BATCHENABLED - Whether Online Batch Server is Enabled

Parameter	BATCHENABLED		
Description	Whether the Online Batch Server is enabled or not.		
Ordinality	Mandatory		
Valid Values	[true false]		
J2EE Web Application Server	WLS WAS WASND		
Tier	BAS BATCH		
Installation Mode	EMBED NATIVE		

A.2.12 BATCHTHREADS - Number of Online Batch Server Threads

Parameter	BATCHTHREADS		
Description	Number of Threads in DEFAULT online threadpool.		
Ordinality	Mandatory		
Valid Values	Default: 5		
J2EE Web Application Server	WLS WAS WASND		
Tier	BAS		
Installation Mode	EMBED NATIVE		

A.2.13 BATCH_DBPASS - Batch User Password

Parameter	BATCH_DBPASS		
Description	Encrypted password for database user used for batch.		
Ordinality	Mandatory		
Valid Values	Encrypted password		
J2EE Web Application Server	Not Applicable		
Tier	BATCH DB		
Installation Mode	Not Applicable		

A.2.14 BATCH_DBUSER - Batch User

Parameter	BATCH_DBUSER
Description	Database user used for batch.
Ordinality	Mandatory
Valid Values	Valid database user
J2EE Web Application Server	Not Applicable
Tier	BATCH DB
Installation Mode	Not Applicable

A.2.15 BATCH_MEMORY_ADDITIONAL_OPT - Threadpool Worker JVM Additional Options

Parameter	BATCH_MEMORY_ADDITIONAL_OPT
Description	Additional JVM Options for Threadpools
Ordinality	Mandatory
Valid Values	Valid Threadpool parameters. For example: BATCH_MEMORY_ADDITIONAL_OPT=-Xdebug -Xnoagent Xrunjdw:transport=dt_socket,address=7757, server=y,suspend=n -Djava.compiler=NONE
J2EE Web Application Server	Not Applicable
Tier	BATCH
Installation Mode	Not Applicable

A.2.16 BATCH_MEMORY_OPT_MAX - Threadpool Worker Java Maximum Heap Size

Parameter	BATCH_MEMORY_OPT_MAX
Description	Maximum JVM Memory for each Threadpool instance
Ordinality	Mandatory
Valid Values	Memory specification (in MB). Default: 1024
J2EE Web Application Server	Not Applicable
Tier	BATCH
Installation Mode	Not Applicable

A.2.17 BATCH_MEMORY_OPT_MAXPERMSIZE - Threadpool Worker Java Maximum Perm Size

Parameter	BATCH_MEMORY_OPT_MAXPERMSIZE
Description	Maximum JVM PermGen for each Threadpool instance
Ordinality	Mandatory
Valid Values	Memory specification (in MB). Default: 192
J2EE Web Application Server	Not Applicable
Tier	BATCH
Installation Mode	Not Applicable

A.2.18 BATCH_MEMORY_OPT_MIN - Threadpool Worker Java Minimum Heap Size

Parameter	BATCH_MEMORY_OPT_MIN
Description	Minimum JVM Memory for each Threadpool instance
Ordinality	Mandatory
Valid Values	Memory specification (in MB). Default: 512
J2EE Web Application Server	Not Applicable
Tier	BATCH
Installation Mode	Not Applicable

A.2.19 BATCH_MODE - Default Mode of Batch

Parameter	BATCH_MODE
Description	Batch Execution Mode for Threadpools
Ordinality	Mandatory
Valid Values	[THIN CLUSTERED]
J2EE Web Application Server	Not Applicable
Tier	BATCH
Installation Mode	Not Applicable

A.2.20 BATCH_ONLINE_LOG_DIR - Online Batch Submission Log Directory

Parameter	BATCH_ONLINE_LOG_DIR
Description	Location of Online Batch Submission logs
Ordinality	Optional
Valid Values	Valid directory
J2EE Web Application Server	WLS WAS WASND
Tier	BAS
Installation Mode	EMBED NATIVE

A.2.21 BATCH_RMI_PORT - RMI Port for Batch

Parameter	BATCH_RMI_PORT
Description	Port number used for communication to Threadpools. This is used for JMX monitoring.
Ordinality	Mandatory
Valid Values	Valid Port Number
J2EE Web Application Server	Not Applicable
Tier	BATCH
Installation Mode	Not Applicable

A.2.22 BSN_APP - Business Server Application Name

Parameter	BSN_APP
Description	Deployed Business Application Server Name
Ordinality	Mandatory
Valid Values	Default: SPLService
J2EE Web Application Server	WLS WAS WASND
Tier	BAS
Installation Mode	EMBED NATIVE

A.2.23 BSN_JMX_RMI_PORT_PERFORMANCE - JMX Port for Business Application Server

Parameter	BSN_JMX_RMI_PORT_PERFORMANCE
Description	JMX Port for Business Application Server monitoring
Ordinality	Optional
Valid Values	Valid open port for JMX
J2EE Web Application Server	WLS WAS WASND
Tier	BAS
Installation Mode	EMBED NATIVE

A.2.24 BSN_JMX_SYSPASS - Password for BAS JMX Monitoring

Parameter	BSN_JMX_SYSPASS
Description	Default encrypted password for JMX monitoring of Business Application Server Name for BSN_JMX_SYSUSER. This is required if BSN_JMX_RMI_PORT_PERFORMANCE is set.
Ordinality	Optional
Valid Values	Encrypted Password
J2EE Web Application Server	WLS WAS WASND
Tier	BAS
Installation Mode	EMBED NATIVE

A.2.25 BSN_JMX_SYSUSER - Default User for BSN JMX Monitoring

Parameter	BSN_JMX_SYSUSER
Description	Default user for JMX monitoring of Business Application Server Name. This is required if BSN_JMX_RMI_PORT_PERFORMANCE is set.
Ordinality	Optional
Valid Values	Administration User
J2EE Web Application Server	WLS WAS WASND
Tier	BAS
Installation Mode	EMBED NATIVE

A.2.26 BSN_NODENAME - IBM WebSphere Node Name

Parameter	BSN_NODENAME
Description	IBM WebSphere Node to deploy Business Application Server to.
Ordinality	Mandatory
Valid Values	Valid IBM WebSphere Node Names
J2EE Web Application Server	WAS WASND
Tier	BAS
Installation Mode	EMBED

A.2.27 BSN_SVRNAME - IBM WebSphere Server Name

Parameter	BSN_SVRNAME
Description	IBM WebSphere Server Name used to deploy Business Application Server to.
Ordinality	Mandatory
Valid Values	Valid IBM WebSphere Server Names
J2EE Web Application Server	WAS WASND
Tier	BAS
Installation Mode	EMBED

A.2.28 BSN_WASBOOTSTRAPPORt - Bootstrap Port

Parameter	BSN_WASBOOTSTARPPORT
Description	IBM WebSphere Server Bootstrap Port used for Business Application Server.
Ordinality	Mandatory
Valid Values	Valid IBM WebSphere Bootstrap Ports
J2EE Web Application Server	WAS WASND
Tier	BAS
Installation Mode	EMBED

A.2.29 BSN_WLHOST - Business App Server Host

Parameter	BSN_WLHOST
Description	Oracle WebLogic host name for Business Application Server. For native and/or clustered installations this setting should be set to localhost.
Ordinality	Mandatory
Valid Values	Default: Current Host Name
J2EE Web Application Server	WLS
Tier	BAS
Installation Mode	EMBED NATIVE

A.2.30 BSN_WLS_SVRNAME - Oracle WebLogic Server Name

Parameter	BSN_WLS_SVRNAME
Description	Oracle WebLogic server name for Business Application Server. For native and/or clustered installations this setting should be set to the server or cluster created for the deployment.
Ordinality	Mandatory
Valid Values	Default: myserver
J2EE Web Application Server	WLS
Tier	BAS
Installation Mode	EMBED NATIVE

A.2.31 CERT_IDENT_KS_ALIAS - SSL Certificate Keystore Alias

Parameter	CERT_IDENT_KS_ALIAS
Description	Alias used for SSL Keystore.
Ordinality	Mandatory for SSL implementations
J2EE Web Application Server	WLS
Tier	WEB BAS IWS MOB
Installation Mode	EMBED

A.2.32 CERT_IDENT_KS_FILE - SSL Keystore File

Parameter	CERT_IDENT_KS_FILE
Description	Full path to SSL Keystore file
Ordinality	Mandatory for SSL implementations
J2EE Web Application Server	WLS
Tier	WEB BAS IWS MOB
Installation Mode	EMBED

A.2.33 CERT_IDENT_KS_PWD - SSL Keystore Password

Parameter	CERT_IDENT_KS_PWD
Description	Full path to SSL Keystore file
Ordinality	Mandatory for SSL implementations
J2EE Web Application Server	WLS
Tier	WEB BAS IWS MOB
Installation Mode	EMBED

A.2.34 CERT_IDENT_KS_TYPE - SSL Keystore Type

Parameter	CERT_IDENT_KS_TYPE
Description	SSL Keystore file type supported by the J2EE Web Application Server.
Ordinality	Mandatory for SSL implementations
J2EE Web Application Server	WLS
Tier	WEB BAS IWS MOB
Installation Mode	EMBED

A.2.35 CERT_INSTALL_SCRIPT - Install SSL Keystore

Parameter	CERT_IDENT_KS_SCRIPT
Description	Whether the SSL should be installed by the installer or manually installed. If set to true then the product installer will install the demonstration certificate. Set to false when providing a production certificate.

Ordinality	Mandatory for SSL implementations
Valid Values	[true false]
J2EE Web Application Server	WLS
Tier	WEB BAS IWS MOB
Installation Mode	EMBED

A.2.36 CERT_KS - SSL Keystore Type

Parameter	CERT_KS
Description	Keystore Type used for generating keystore
Ordinality	Mandatory for SSL implementations
Valid Values	[DEMO PROD ²⁸]
J2EE Web Application Server	WLS
Tier	WEB BAS IWS MOB
Installation Mode	EMBED

A.2.37 CERT_TRUST_KS_ALIAS - SSL Trust Alias

Parameter	CERT_TRUST_KS_ALIAS
Description	Full path to SSL Trust Keystore alias
Ordinality	Mandatory for SSL implementations
J2EE Web Application Server	WLS
Tier	WEB BAS IWS MOB
Installation Mode	EMBED

A.2.38 CERT_TRUST_KS_FILE - SSL Trust Keystore File

Parameter	CERT_TRUST_KS_FILE
Description	Full path to SSL Trust Keystore file
Ordinality	Mandatory for SSL implementations
J2EE Web Application Server	WLS

²⁸ This is a suggested value. Values other than DEMO are recognized.

Tier	WEB	BAS	IWS	MOB
Installation Mode	EMBED			

A.2.39 CERT_TRUST_KS_PWD - SSL Trust Keystore Password

Parameter	CERT_TRUST_KS_PWD
Description	Password to SSL Trust Keystore file
Ordinality	Mandatory for SSL implementations
Valid Values	Encrypted Password
J2EE Web Application Server	WLS
Tier	WEB
Installation Mode	EMBED

A.2.40 CERT_TRUST_KS_TYPE - SSL Trust Keystore Type

Parameter	CERT_IDENT_KS_TYPE
Description	SSL Trust Keystore file type
Ordinality	Mandatory for SSL implementations
Valid Values	Keystore types supported by J2EE Web Application Server
J2EE Web Application Server	WLS
Tier	WEB
Installation Mode	EMBED

A.2.41 CLOUD_CUSTOM_WHITE_LIST_PATH - Custom URL Whitelists for Cloud

Parameter	CLOUD_CUSTOM_WHITE_LIST_PATH
Description	The full path to a custom whitelist for aliases for URLs within the product. This whitelist is added to the base product whitelist which is provided in CLOUD_WHITE_LIST_PATH variable. This is primarily for cloud implementations to define URL aliases .
Ordinality	Optional
Valid Values	Full path (including filename to whitelist)
J2EE Web Application Server	WLS

Tier	WEB	BAS	BATCH	MOB
Installation Mode	EMBED	NATIVE		

A.2.42 CLOUD_RESTRICTIONS_URLS_ENABLE - Enable or Disable URL Restrictions

Parameter	CLOUD_RESTRICTIONS_URL_ENABLE			
Description	Whether the whitelists for URL's are enabled.			
Ordinality	Optional			
Valid Values	true false			
J2EE Web Application Server	WLS			
Tier	WEB	BAS	BATCH	MOB
Installation Mode	EMBED	NATIVE		

A.2.43 CLOUD_WHITE_LIST_PATH - URL Whitelists for Cloud

Parameter	CLOUD_WHITE_LIST_PATH			
Description	The full path to a base whitelist for aliases for URLs within the product. This whitelist is added with the custom product whitelist which is provided in CLOUD_CUSTOM_WHITE_LIST_PATH variable. This is primarily for cloud implementations to define URL aliases .			
Ordinality	Optional			
Valid Values	Full path (including filename to whitelist)			
J2EE Web Application Server	WLS			
Tier	WEB	BAS	BATCH	MOB
Installation Mode	EMBED	NATIVE		

A.2.44 CM_INSTALL_SAMPLE - Whether Samples are Installed

Parameter	CM_INSTALL_SAMPLE			
Description	Whether sample code is installed or not. This is done at installation time.			
Ordinality	Mandatory			
Valid Values	true false			

J2EE Web Application Server	WLS	WAS	WASND
Tier	WEB	BAS	BATCH
Installation Mode	EMBED	NATIVE	

A.2.45 CMPDB - Database Type

Parameter	CMPDB
Description	Database Type. This parameter is provided for backward compatibility and is set to ORACLE. This should not be altered.
Ordinality	Mandatory
Valid Values	ORACLE
J2EE Web Application Server	WLS
Tier	BAS
Installation Mode	EMBED
	NATIVE

A.2.46 COHERENCE_CLUSTER_ADDRESS - Multicast Address for Batch Cluster

Parameter	COHERENCE_CLUSTER_ADDRESS
Description	Multicast IP Address for CLUSTERED mode. Specify the multicast IP address that a Socket will listen or publish on.
Ordinality	Mandatory
Valid Values	Valid values are from 224.0.0.0 to 239.255.255.255.
J2EE Web Application Server	Not Applicable
Tier	BATCH
Installation Mode	Not Applicable

A.2.47 COHERENCE_CLUSTER_MODE - Batch Cluster Mode

Parameter	COHERENCE_CLUSTER_MODE
Description	<p>Oracle Coherence mode. Coherence may be configured to operate in either development or production mode. These modes do not limit access to features, but instead alter some default configuration settings. For instance, development mode allows for faster cluster startup to ease the development process.</p> <p>The development mode is used for all pre-production activities, such as development and testing. This is an important safety feature because development nodes are restricted from joining with production nodes. Development mode is the default mode. Production mode (prod) must be explicitly specified when using Coherence in a production environment.</p>
Ordinality	Mandatory
Valid Values	[dev prod]
J2EE Web Application Server	Not Applicable
Tier	BATCH
Installation Mode	Not Applicable

A.2.48 COHERENCE_CLUSTER_NAME - Batch Cluster Name

Parameter	COHERENCE_CLUSTER_NAME
Description	Unique Cache name for Coherence Clusters.
Ordinality	Mandatory
Valid Values	Any string value. It is recommended to use the SPLENVIRON value, optionally, with the database schema owner as a unique identifier. For example: DEV.SPLADM
J2EE Web Application Server	Not Applicable
Tier	BATCH
Installation Mode	Not Applicable

A.2.49 COHERENCE_CLUSTER_PORT - Batch Cluster Port Number

Parameter	COHERENCE_CLUSTER_PORT
Description	Unique Cache port for the Coherence Cluster.
Ordinality	Mandatory
Valid Values	Any open relevant port unique to the COHERENCE_CLUSTER_NAME.
J2EE Web Application Server	Not Applicable
Tier	BATCH
Installation Mode	Not Applicable

A.2.50 CONTEXTFACTORY - Context Factory for Mobile Application

Parameter	CONTEXTFACTORY
Description	ContextFactory used for Mobile Integration
Ordinality	Mandatory
Valid Values	Refer to spl.mwm.abr.contextFactory - ABR Context Factory for more details.
J2EE Web Application Server	WLS WAS WASND
Tier	MOB
Installation Mode	EMBED NATIVE

A.2.51 DBCONNECTION - JDBC Connection String

Parameter	DBCONNECTION
Description	<p>Generated Database JDBC string.</p> <p>This is generated from the DBSERVER / DBPORT / DBNAME or DB_OVERRIDE_CONNECTION.</p> <p>As this is generated, it should not be altered.</p> <p>Customers using Native mode installation can replace this connection with JDBC Data Sources, if desired.</p>
Ordinality	Mandatory
Valid Values	Generated URL
J2EE Web Application Server	WLS WAS WASND
Tier	BAS BATCH DB
Installation Mode	EMBED NATIVE

A.2.52 DBDRIVER - Database Driver

Parameter	DBDRIVER
Description	<p>Database Driver to use.</p> <p>Automatically generated by installation.</p> <p>This should not be altered.</p>
Ordinality	Mandatory
Valid Values	Generated URL
J2EE Web Application Server	WLS WAS WASND
Tier	BAS BATCH DB
Installation Mode	EMBED NATIVE

A.2.53 DBNAME - Database Name

Parameter	DBNAME
Description	Oracle Database Instance Name. Customers using Native mode installation can ignore this value if using JDBC Data Sources.
Ordinality	Mandatory
Valid Values	Valid Database instance name
J2EE Web Application Server	WLS WAS WASND
Tier	BAS BATCH DB
Installation Mode	EMBED NATIVE

A.2.54 DBPASS - Online Database User Password

Parameter	DBPASS
Description	Encrypted database user password for the online component of the product. Password for DBUSER.
Ordinality	Mandatory
Valid Values	Encrypted Password
J2EE Web Application Server	WLS WAS WASND
Tier	BAS BATCH DB
Installation Mode	EMBED NATIVE

A.2.55 DBPASS_GEOCODE_WLS - GEOCODE Database Password

Parameter	DBPASS_GEOCODE_WLS
Description	Encrypted database user password for the GEOCODE integration. Password for DBUSER_GEOCODE.
Ordinality	Mandatory
Valid Values	Encrypted Password
J2EE Web Application Server	WLS WAS WASND
Tier	MOB DB
Installation Mode	EMBED NATIVE

A.2.56 DBPASS_MDS - MDS Database Password

Parameter	DBPASS_MDS
Description	Encrypted database user password for the SOA Suite Meta Data Service (MDS) integration. Password for DBUSER_MDS. This password was specified as part of the SOA Suite database installation process for the prefix_MDS user. This is only valid for products that include Oracle SOA Suite. This is used for deployment of content to Oracle SOA Suite for integration.
Ordinality	Mandatory
Valid Values	Encrypted Password
J2EE Web Application Server	WLS WAS WASND
Tier	BAS BATCH DB
Installation Mode	EMBED NATIVE

A.2.57 DBPASS_ORASDPM - DPM Database Password

Parameter	DBPASS_ORASDPM
Description	<p>Encrypted database user password for the SOA Suite User Message Services (DPM) integration. Password for DBUSER_ORASDPM.</p> <p>This password was specified as part of the SOA Suite database installation process for the prefix_ORASDPM user.</p> <p>This is only valid for products that include Oracle SOA Suite. This is used for deployment of content to Oracle SOA Suite for integration.</p>
Ordinality	Mandatory
Valid Values	Encrypted Password
J2EE Web Application Server	WLS WAS WASND
Tier	BAS BATCH DB
Installation Mode	EMBED NATIVE

A.2.58 DBPASS_OSB - OSB Database Password

Parameter	DBPASS_OSB
Description	<p>Encrypted database user password for the Oracle Service Bus (OSB) integration. Password for DBUSER_OSB.</p> <p>This password was specified as part of the Oracle Service Bus installation for the OSB database user.</p> <p>This is only valid for products that include Oracle Service Bus. This is used for deployment of content to Oracle Service Bus for integration.</p> <p>This is not used for the Oracle Service Bus Adapters for Oracle Utilities.</p>
Ordinality	Mandatory
Valid Values	Encrypted Password
J2EE Web Application Server	WLS WAS WASND
Tier	BAS BATCH DB
Installation Mode	EMBED NATIVE

A.2.59 DBPASS_SOAINFRA - SOA Database Password

Parameter	DBPASS_SOAINFRA
Description	<p>Encrypted database user password for the SOA Suite integration. Password for DBUSER_SOAINFRA.</p> <p>This password was specified as part of the SOA Suite database installation process for the prefix_SOAINFRA user.</p> <p>This is only valid for products that include Oracle SOA Suite. This is used for deployment of content to Oracle SOA Suite for integration.</p>
Ordinality	Mandatory
Valid Values	Encrypted Password
J2EE Web Application Server	WLS WAS WASND
Tier	BAS BATCH DB
Installation Mode	EMBED NATIVE

A.2.60 DBPORT - Database Listener Port

Parameter	DBPORT
Description	<p>Oracle Listener port for connection to the database.</p> <p>Customers using Native mode installation can ignore this value if using JDBC Data Sources.</p>
Ordinality	Mandatory
Valid Values	Valid Port Number
J2EE Web Application Server	WLS WAS WASND
Tier	BAS BATCH DB
Installation Mode	EMBED NATIVE

A.2.61 DBSERVER - Database Server

Parameter	DBSERVER
Description	Oracle Database Host Name. Customers using Native mode installation can ignore this value if using JDBC Data Sources.
Ordinality	Mandatory
Valid Values	Valid Host Name
J2EE Web Application Server	WLS WAS WASND
Tier	BAS BATCH DB
Installation Mode	EMBED NATIVE

A.2.62 DBURL_GEOCODE - GEOCODE JDBC URL

Parameter	DBURL_GEOCODE
Description	Oracle Database JDBC URL used for Geocoding. This is set for products using Oracle Spatial.
Ordinality	Mandatory
Valid Values	Valid JDBC URL
J2EE Web Application Server	WLS WAS WASND
Tier	BAS BATCH DB
Installation Mode	EMBED NATIVE

A.2.63 DBURL_OSB - OSB JDBC URL

Parameter	DBURL_OSB
Description	Oracle Database JDBC URL for Oracle Service Bus. This is used for deploying content to Oracle Service Bus.
Ordinality	Mandatory
Valid Values	Valid JDBC URL
J2EE Web Application Server	WLS WAS WASND
Tier	BAS BATCH DB
Installation Mode	EMBED NATIVE

A.2.64 DBURL_SOA - SOA Suite JDBC URL

Parameter	DBURL_SOA
Description	Oracle Database JDBC URL for Oracle SOA Suite. This is used for deploying content to Oracle SOA Suite.
Ordinality	Mandatory
Valid Values	Valid JDBC URL
J2EE Web Application Server	WLS WAS WASND
Tier	BAS BATCH DB
Installation Mode	EMBED NATIVE

A.2.65 DBUSER - Online Database User

Parameter	DBUSER
Description	Database User, with Read/Write permissions used for pooled connections for online transactions.
Ordinality	Mandatory
Valid Values	Valid Database User used in installation
J2EE Web Application Server	WLS WAS WASND
Tier	BAS BATCH DB
Installation Mode	EMBED NATIVE

A.2.66 DBUSER_GEOCODE - GECODE Database User

Parameter	DBUSER_GEOCODE
Description	Database User, with connection to Geocode Database.
Ordinality	Mandatory
Valid Values	Valid Database User on target database
J2EE Web Application Server	WLS WAS WASND
Tier	BAS BATCH DB
Installation Mode	EMBED NATIVE

A.2.67 DBUSER_MDS - SOA MDS Database User

Parameter	DBPASS_MDS
Description	<p>Database user password for the SOA Suite Meta Data Services (MDS) integration.</p> <p>This userID was specified as part of the SOA Suite database installation process for the <code>prefix_MDS</code> user.</p> <p>This is only valid for products that include Oracle SOA Suite. This is used for deployment of content to Oracle SOA Suite for integration.</p>
Ordinality	Mandatory
Valid Values	Valid Database User (<code>prefix_MDS</code>) on target database
J2EE Web Application Server	WLS WAS WASND
Tier	BAS BATCH DB
Installation Mode	EMBED NATIVE

A.2.68 DBUSER_ORASDPM - DPM Database User

Parameter	DBPASS_ORASDPM
Description	<p>Database user password for the SOA Suite User Messaging Services (DPM) integration.</p> <p>This userID was specified as part of the SOA Suite database installation process for the <code>prefix_ORASDPM</code> user.</p> <p>This is only valid for products that include Oracle SOA Suite. This is used for deployment of content to Oracle SOA Suite for integration.</p>
Ordinality	Mandatory
Valid Values	Valid Database User (<code>prefix_ORASDPM</code>) on target database
J2EE Web Application Server	WLS WAS WASND
Tier	BAS BATCH DB
Installation Mode	EMBED NATIVE

A.2.69 DBUSER_OSB - OSB Database User

Parameter	DBPASS_OSB
Description	<p>Database user password for the Oracle Service Bus integration.</p> <p>This userID was specified as part of the Oracle Service Bus database installation process.</p> <p>This is only valid for products that include Oracle Service Bus. This is used for deployment of content to Oracle Service Bus for integration.</p>
Ordinality	Mandatory
Valid Values	Valid Database User on target database
J2EE Web Application Server	WLS WAS WASND
Tier	BAS BATCH DB
Installation Mode	EMBED NATIVE

A.2.70 DBUSER_SOAINFRA - SOA Database User

Parameter	DBPASS_SOAINFRA
Description	<p>Database user password for the SOA Suite integration.</p> <p>This userID was specified as part of the SOA Suite database installation process for the <code>prefix_SOAINFRA</code> user.</p> <p>This is only valid for products that include Oracle SOA Suite. This is used for deployment of content to Oracle SOA Suite for integration.</p>
Ordinality	Mandatory
Valid Values	Valid Database User (<code>prefix_SOAINFRA</code>) on target database
J2EE Web Application Server	WLS WAS WASND
Tier	BAS BATCH DB
Installation Mode	EMBED NATIVE

A.2.71 DB_OVERRIDE_CONNECTION - Custom JDBC URL

Parameter	DB_OVERRIDE_CONNECTION
Description	<p>Database JDBC Override string.</p> <p>For customers using Oracle 12c, use a string in the following format to support Pluggable Databases:</p> <p><code>jdbc:oracle:thin:@//<host>:<port>/<dbname></code></p> <p>Customers using Native mode installation can replace this connection with JDBC Data Sources, if desired.</p>
Ordinality	Mandatory
Valid Values	Valid JDBC URL.
J2EE Web Application Server	WLS WAS WASND
Tier	BAS BATCH DB
Installation Mode	EMBED NATIVE

A.2.72 DESC - Environment Description

Parameter	DESC
Description	Environment Description. Used for documentation purposes only.
Ordinality	Optional
Valid Values	String Value
J2EE Web Application Server	Not Applicable
Tier	Not Applicable
Installation Mode	Not Applicable

A.2.73 DIALECT - Hibernate Dialect

Parameter	DIALECT
Description	<p>Hibernate Dialect</p> <p>This is the database dialect used by Hibernate to process database requests. This is automatically generated by the installer and should not be altered.</p>
Ordinality	Mandatory
Valid Values	Valid Hibernate Dialects
J2EE Web Application Server	WLS WAS WASND
Tier	BAS BATCH DB
Installation Mode	EMBED NATIVE

A.2.74 DIRSEP - Directory Separator

Parameter	DIRSEP
Description	<p>Directory Separator</p> <p>This is an internal setting that sets the directory separator applicable for the platform. This setting is used by various scripts to set the paths correctly for the operating system.</p> <p>This setting is automatically generated at installation time and should not be altered.</p>
Ordinality	Mandatory
Valid Values	Directory Separator character
J2EE Web Application Server	WLS WAS WASND
Tier	WEB BAS IWS XAI BATCH MOB
Installation Mode	EMBED NATIVE

A.2.75 DOC1BILLSCRIPT - Name of External Print Script

Parameter	DOC1BILLSCRIPT
Description	This setting sets the name of the external printing script used for printing extracts using Oracle Documaker. This is generated by individual products that support this feature.
Ordinality	Mandatory
Valid Values	Name of supplied script
J2EE Web Application Server	WLS WAS WASND
Tier	WEB BAS IWS XAI BATCH MOB
Installation Mode	EMBED NATIVE

A.2.76 DOC1SCRIPT - Name of Generic Print Script

Parameter	DOC1SCRIPT
Description	This setting sets the name of the generic printing script used for extracts using Oracle Documaker. This is generated by individual products that support this feature.
Ordinality	Mandatory
Valid Values	Name of supplied script
J2EE Web Application Server	WLS WAS WASND
Tier	WEB BAS IWS XAI BATCH MOB
Installation Mode	EMBED NATIVE

A.2.77 ENCODING - Whether Encryption is Enabled

Parameter	ENCODING
Description	Enables or Disables encryption across the product. By default encryption is enabled (true) and is recommended to be enabled for all environments.
Ordinality	Mandatory
Valid Values	[true false]
J2EE Web Application Server	WLS WAS WASND
Tier	WEB BAS IWS XAI BATCH MOB
Installation Mode	EMBED NATIVE

A.2.78 ENVIRONMENT_ID - Environment Identifier

Parameter	ENVIRONMENT_ID
Description	Unique identifier for each environment or copy of the product. This is specified at installation time to link disparate installations into a single environment for management purposes. This setting is used by the Oracle Application Management Pack for Oracle Utilities within Oracle Enterprise Manager to link disparate targets across a number of hosts into a single Oracle Utilities Environment target.
Ordinality	Mandatory
Valid Values	Autogenerated
J2EE Web Application Server	WLS WAS WASND
Tier	WEB BAS IWS XAI BATCH
Installation Mode	EMBED NATIVE

A.2.79 FW_VERSION - Oracle Utilities Application Framework Version

Parameter	FWVERSION
Description	<p>Oracle Utilities Application Version</p> <p>This is an internal setting that is generated upon installation of the product, service pack installation or upgrade installation.</p> <p>This setting is automatically generated at installation time and should not be altered.</p>
Ordinality	Mandatory
Valid Values	Valid Oracle Utilities Application Framework version
J2EE Web Application Server	Not Applicable
Tier	Not Applicable
Installation Mode	Not Applicable

A.2.80 FW_VERSION_NUM - Oracle Utilities Application Framework Version Identifier

Parameter	FW_VERSION_NUM
Description	<p>Oracle Utilities Application Version</p> <p>This is an internal setting that is generated upon installation of the product, service pack installation or upgrade installation.</p> <p>This setting is automatically generated at installation time and should not be altered.</p>
Ordinality	Mandatory
Valid Values	Valid Oracle Utilities Application Framework version
J2EE Web Application Server	Not Applicable
Tier	Not Applicable
Installation Mode	Not Applicable

A.2.81 GIS - GIS Support

Parameter	GIS
Description	Enables or Disables GIS support within the product. This setting is only used by products that use GIS integration. Setting this value to true enabled all other GIS settings.
Ordinality	Mandatory
Valid Values	[true false]
J2EE Web Application Server	WLS
Tier	WEB BAS BATCH
Installation Mode	EMBED NATIVE

A.2.82 GIS_URL - GIS Service URL

Parameter	GIS_URL
Description	Specifies the GIS JNDI URL used for connections. This setting is only used by products that use GIS integration. This setting is only used if <code>GIS</code> is set to true.
Ordinality	Mandatory
Valid Values	Valid JNDI URL
J2EE Web Application Server	WLS
Tier	WEB BAS BATCH
Installation Mode	EMBED NATIVE

A.2.83 GIS_WLSYSPASS - GIS WebLogic System Password

Parameter	GIS_WLSYSPASS
Description	Encrypted JNDI Password for GIS integration. This setting is only used by products that use GIS integration. This setting is only used if GIS is set to true.
Ordinality	Mandatory
Valid Values	Valid Encrypted Password
J2EE Web Application Server	WLS
Tier	WEB BAS BATCH
Installation Mode	EMBED NATIVE

A.2.84 GIS_WLSYSUSER - GIS WebLogic System User ID

Parameter	GIS_WLSYSUSER
Description	Encrypted JNDI User for GIS integration. This setting is only used by products that use GIS integration. This setting is only used if GIS is set to true.
Ordinality	Mandatory
Valid Values	Valid Encrypted User
J2EE Web Application Server	WLS
Tier	WEB BAS BATCH
Installation Mode	EMBED NATIVE

A.2.85 GLOBAL_JVMARGS - Additional JVM Arguments

Parameter	GLOBAL_JVMARGS
Description	Specific additional JVM options for the online component of the product for Oracle JVM (to enable advanced features)
Ordinality	Mandatory
Valid Values	This is generated
J2EE Web Application Server	WLS
Tier	WEB BAS
Installation Mode	EMBED NATIVE

A.2.86 help - Name of Online Help WAR File

Parameter	help
Description	Name of Help WAR file. Used in build of help application. This is used for IBM WebSphere implementations using the SPLHelp engine
Ordinality	Mandatory
Valid Values	This value is automatically generated
J2EE Web Application Server	WAS WASND
Tier	WEB
Installation Mode	EMBED NATIVE

A.2.87 HEADEND_CD_CB - Headend System URI for SOA Configuration Plan (CD_CB)

Parameter	HEADEND_CD_CB
Description	URI as configure in SOA Suite Configuration Plan for Headend System for the CD_DB interface (Echelon). This setting is only available to products interfacing to headend systems using SOA Suite.
Ordinality	Mandatory
Valid Values	Valid SOA Suite URI for CD_DB interface.
J2EE Web Application Server	WLS WAS WASND
Tier	BAS
Installation Mode	EMBED NATIVE

A.2.88 HEADEND_MR_CB - Headend System URI for SOA Configuration Plan (MR_CB)

Parameter	HEADEND_MR_CB
Description	URI as configure in SOA Suite Configuration Plan for Headend System for the MR_DB interface (Echelon). This setting is only available to products interfacing to head end systems using SOA Suite.
Ordinality	Mandatory
Valid Values	Valid SOA Suite URI for MR_DB interface.
J2EE Web Application Server	WLS WAS WASND
Tier	BAS
Installation Mode	EMBED NATIVE

A.2.89 HIBERNATE_JAR_DIR - Location of Hibernate JAR files

Parameter	HIBERNATE_JAR_DIR
Description	Location of the Hibernate JAR files. This setting is used by the installer to copy the relevant files to the desired locations for deployment. This setting is only used at installation time but is registered for potential post release use.
Ordinality	Mandatory
Valid Values	Valid location of Hibernate JAR Files as outlined in the product Installation Guide.
J2EE Web Application Server	WLS WAS WASND
Tier	BAS BATCH IWS
Installation Mode	EMBED NATIVE

A.2.90 HIGHVALUE - Language Specific Highvalues

Parameter	HIGHVALUE
Description	High value used for SQL queries. This is autogenerated at installation time.
Ordinality	Mandatory
Valid Values	This value is automatically generated and should not be altered.
J2EE Web Application Server	WLS WAS WASND
Tier	WEB BAS IWS BATCH MOB
Installation Mode	EMBED NATIVE

A.2.91 IWS_JDBC_NAME - JNDI Name for the IWS Connection Pools

Parameter	IWS_JDBC_NAME
Description	This is the JDBC Data Source connection name used for Inbound Web Services. The JDBC Data Source should be created prior to setting this value using the Configuring JDBC Data Sources instructions.
Ordinality	Optional
Valid Values	Valid fully qualified JNDI name for JDBC Data Source.

J2EE Web Application Server	WLS
Tier	IWS
Installation Mode	EMBED NATIVE

A.2.92 IPCSTARTPORT - Starting IPC Port for Scheduler

Parameter	IPCSTARTPORT
Description	Starting port number for Interprocess Communications (IPC) for Scheduler
Ordinality	Mandatory
Valid Values	Valid open port numbers
J2EE Web Application Server	WLS WAS WASND
Tier	MOB
Installation Mode	EMBED NATIVE

A.2.93 IWSWAR - Name of Inbound Web Services WAR

Parameter	IWSWAR
Description	Default Name for Inbound Web Services Application Name.
Ordinality	Mandatory
Valid Values	Valid Server Application Names
J2EE Web Application Server	WLS WAS WASND
Tier	IWS
Installation Mode	EMBED NATIVE

A.2.94 JAVAENCODING - Java Language Encoding

Parameter	JAVAENCODING
Description	Encoding string for Java to support appropriate character sets.
Ordinality	Mandatory
Valid Values	Valid Java Encoding (java.lang). Default: UTF8
J2EE Web Application	WLS WAS WASND

Server					
Tier	WEB BAS IWS BATCH MOB				
Installation Mode	EMBED NATIVE				

A.2.95 JAVA_HOME - Location of Java SDK

Parameter	JAVA_HOME				
Description	Location of JDK for use with product				
Ordinality	Mandatory				
Valid Values	Valid JAVA_HOME location				
J2EE Web Application Server	WLS WAS WASND				
Tier	WEB BAS IWS BATCH MOB				
Installation Mode	EMBED NATIVE				

A.2.96 JAVA_VENDOR - Java Vendor

Parameter	JAVA_VENDOR				
Description	JVM Vendor				
Ordinality	Mandatory				
Valid Values	Generated and used in other utilities				
J2EE Web Application Server	WLS WAS WASND				
Tier	WEB BAS IWS BATCH MOB				
Installation Mode	EMBED NATIVE				

A.2.97 JAVA_VERSION - JVM Version String

Parameter	JAVA_VERSION				
Description	Fully qualified JVM version string				
Ordinality	Mandatory				
Valid Values	Generated and used in other utilities				
J2EE Web Application Server	WLS WAS WASND				
Tier	WEB BAS IWS BATCH MOB				
Installation Mode	EMBED NATIVE				

A.2.98 JAVA_VERSION_MAIN - Abbreviated JVM Version

Parameter	JAVA_VERSION_MAIN
Description	Abbreviated JVM version string
Ordinality	Mandatory
Valid Values	Generated and used in other utilities
J2EE Web Application Server	WLS WAS WASND
Tier	WEB BAS IWS BATCH MOB
Installation Mode	EMBED NATIVE

A.2.99 JDBC_NAME - JNDI Name for the Online JDBC Data Source

Parameter	JDBC_NAME
Description	This is the JDBC Data Source connection name used for Online channel. The JDBC Data Source should be created prior to setting this value using the Configuring JDBC Data Sources instructions.
Ordinality	Optional
Valid Values	Valid fully qualified JNDI name for JDBC Data Source.
J2EE Web Application Server	WLS
Tier	WEB
Installation Mode	EMBED NATIVE

A.2.100 JNDI_GEOCODE - Geocode Data Source JNDI

Parameter	JNDI_GEOCODE
Description	JNDI name for the Geocode Data Source. This parameter is used for the Geocode interface. This parameter is only valid for products that use the Geocode interface.
Ordinality	Mandatory
Valid Values	Valid JNDI for Geocode Data Source
J2EE Web Application Server	WLS WAS WASND

Tier	BAS	BATCH	MOB
Installation Mode	EMBED	NATIVE	

A.2.101 JNDI_OSB - OSB Data Source JNDI

Parameter	JNDI_OSB		
Description	JNDI name for the Oracle Service Bus Data Source. This parameter is used for the Oracle Service Bus interface. This parameter is only valid for products that ship integration that requires Oracle Service Bus.		
Ordinality	Mandatory		
Valid Values	Valid JNDI for Oracle Service Bus Data Source		
J2EE Web Application Server	WLS WAS WASND		
Tier	BAS BATCH		
Installation Mode	EMBED	NATIVE	

A.2.102 JVM_ADDITIONAL_OPT - Child JVM Additional Options

Parameter	JVM_ADDITIONAL_OPT		
Description	Additional Java options for the Child JVM. Allows implementations to add additional java options for the Child JVM. This parameter is only valid for product that support COBOL based extensions.		
Ordinality	Mandatory		
Valid Values	Valid Java options (refer JVM vendor documentation)		
J2EE Web Application Server	WLS WAS WASND		
Tier	BAS		
Installation Mode	EMBED	NATIVE	

A.2.103 JVMCOMMAND - Generated Child JVM Command

Parameter	JVMCOMMAND
Description	Command executed to initiate to start Child JVM. This parameter is automatically generated. This parameter is only valid for product that support COBOL based extensions.
Ordinality	Mandatory
Valid Values	Generated command line
J2EE Web Application Server	WLS WAS WASND
Tier	BAS
Installation Mode	EMBED NATIVE

A.2.104 JVMMEMORYARG - Child JVM Memory Allocation

Parameter	JVMMEMORYARG
Description	Maximum memory (in MB) to be allocated per Child JVM. This parameter is only valid for product that support COBOL based extensions.
Ordinality	Mandatory
Valid Values	Valid memory specification. Default: 512
J2EE Web Application Server	WLS WAS WASND
Tier	BAS
Installation Mode	EMBED NATIVE

A.2.105 KS_ALIAS - Key Alias

Parameter	KS_ALIAS
Description	Key Alias contained in keystore used by <code>keytool</code> . It is recommended to retain the default setting, unless an alternative is desired.
Ordinality	Mandatory
Valid Values	Valid alias. Default: ouaf.system
J2EE Web Application Server	WLS WAS WASND
Tier	WEB BAS IWS BATCH MOB
Installation Mode	EMBED NATIVE

A.2.106 KS_ALIAS_KEYALG - Key Algorithm

Parameter	KS_ALIAS_KEYALG
Description	Key Alias Algorithm contained in keystore used by <code>keytool</code> .
Ordinality	Mandatory
Valid Values	Valid algorithm. Default: AES
J2EE Web Application Server	WLS WAS WASND
Tier	WEB BAS IWS BATCH MOB
Installation Mode	EMBED NATIVE

A.2.107 KS_ALIAS_KEYSIZE - Keysize

Parameter	KS_ALIAS_KEYSIZE
Description	Keysize strength contained in keystore used by <code>keytool</code> .
Ordinality	Mandatory
Valid Values	Valid keysizes. Default: 128
J2EE Web Application Server	WLS WAS WASND
Tier	WEB BAS IWS BATCH MOB
Installation Mode	EMBED NATIVE

A.2.108 KS_HMAC_ALIAS - HMAC Key Alias

Parameter	KS_HMAC_ALIAS
Description	Key HMAC Alias contained in keystore used by keytool. It is recommended to retain the default setting, unless an alternative is desired.
Ordinality	Mandatory
Valid Values	Valid alias. Default: ouaf.system.hmac
J2EE Web Application Server	WLS WAS WASND
Tier	WEB BAS IWS BATCH MOB
Installation Mode	EMBED NATIVE

A.2.109 KS_HMAC_ALIAS_KEYALG - HMAC Key Algorithm

Parameter	KS_HMAC_ALIAS_KEYALG
Description	Key HMAC Alias Algorithm contained in keystore used by keytool.
Ordinality	Mandatory
Valid Values	Valid algorithm. Default: HmacSHA256
J2EE Web Application Server	WLS WAS WASND
Tier	WEB BAS IWS BATCH MOB
Installation Mode	EMBED NATIVE

A.2.110 KS_HMAC_ALIAS_KEYSIZE - HMAC Keysize

Parameter	KS_HMAC_ALIAS_KEYSIZE
Description	HMAC Keysize strength used by keystore used by keytool.
Ordinality	Mandatory
Valid Values	Valid keysize. Default: 256
J2EE Web Application Server	WLS WAS WASND
Tier	WEB BAS IWS BATCH MOB
Installation Mode	EMBED NATIVE

A.2.111 KS_KEYSTORE_FILE - Keystore File Name

Parameter	KS_KEYSTORE_FILE				
Description	Keystore File used by keytool.				
Ordinality	Mandatory				
Valid Values	Valid location and file name for keystore. Linux: <code>\$SPLEBASE/ks/.ouaf_keystore</code> Windows: <code>%SPLEBASE%\ks\.ouaf_keystore</code>				
J2EE Web Application Server	WLS WAS WASND				
Tier	WEB BAS IWS BATCH MOB				
Installation Mode	EMBED NATIVE				

A.2.112 KS_MODE - Key Padding Mode

Parameter	KS_MODE				
Description	Key Padding Mode				
Ordinality	Mandatory				
Valid Values	Valid Padding for Keystore. Default: CBC				
J2EE Web Application Server	WLS WAS WASND				
Tier	WEB BAS IWS BATCH MOB				
Installation Mode	EMBED NATIVE				

A.2.113 KS_PADDING - Key Padding Algorithm

Parameter	KS_PADDING				
Description	Key Padding Algorithm used for key generation				
Ordinality	Mandatory				
Valid Values	Valid Padding Algorithm for Keystore. Default: PKCS5Padding				
J2EE Web Application Server	WLS WAS WASND				
Tier	WEB BAS IWS BATCH MOB				
Installation Mode	EMBED NATIVE				

A.2.114 KS_STOREPASS_FILE - Key Password Store Pass

Parameter	KS_STOREPASS_FILE
Description	Password Keystore File used by keytool.
Ordinality	Mandatory
Valid Values	Valid location and file name for keystore. <u>Linux:</u> <code>\$SPLEBASE/ks/.ouaf_storepass</code> <u>Windows:</u> <code>%SPLEBASE%\ks\.ouaf_storepass</code>
J2EE Web Application Server	WLS WAS WASND
Tier	WEB BAS IWS BATCH MOB
Installation Mode	EMBED NATIVE

A.2.115 KS_STORETYPE - Key Store Type

Parameter	KS_STORETYPE
Description	Keystore Store Type used by keytool.
Ordinality	Mandatory
Valid Values	Valid Key Store Type. Default: JCEKS
J2EE Web Application Server	WLS WAS WASND
Tier	WEB BAS IWS BATCH MOB
Installation Mode	EMBED NATIVE

A.2.116 LD_LIBRARY_PATH - Library Path for Windows/Linux/Solaris

Parameter	LD_LIBRARY_PATH				
Description	Generated Library Path for Windows, Linux and Solaris				
Ordinality	Mandatory				
Valid Values	This value is generated by the product installer.				
J2EE Web Application Server	WLS WAS WASND				
Tier	WEB BAS IWS BATCH MOB				
Installation Mode	EMBED NATIVE				

A.2.117 LIBPATH - Library Path for AIX

Parameter	LIBPATH				
Description	Generated Library Path for AIX				
Ordinality	Mandatory				
Valid Values	This value is generated by the product installer.				
J2EE Web Application Server	WLS WAS WASND				
Tier	WEB BAS IWS BATCH MOB				
Installation Mode	EMBED NATIVE				

A.2.118 MAPDIR - Location of Map Files Used for Scheduler

Parameter	MAPDIR				
Description	Location of local Map file used by Scheduler. This parameter only applies to products that use the Scheduler.				
Ordinality	Mandatory				
Valid Values	Fully qualified directory holding map files				
J2EE Web Application Server	WLS WAS WASND				
Tier	MOB				
Installation Mode	EMBED NATIVE				

A.2.119 MAPVIEWER_EAR - Location of Mapviewer EAR File

Parameter	MAPVIEWER_EAR
Description	Location of MapViewer EAR file. This parameter only applies to products that use the Scheduler.
Ordinality	Mandatory
Valid Values	Fully qualified directory EAR file
J2EE Web Application Server	WLS WAS WASND
Tier	MOB
Installation Mode	EMBED NATIVE

A.2.120 MAPVIEWER_ISLOCAL - Deploy Mapviewer Locally

Parameter	MAPVIEWER_ISLOCAL
Description	Whether the MapViewer application is to be deployed within the same server as the product. This parameter only applies to products that use the Scheduler.
Ordinality	Mandatory
Valid Values	[true false]
J2EE Web Application Server	WLS WAS WASND
Tier	MOB
Installation Mode	EMBED NATIVE

A.2.121 MAXPROCESSINGTIME - Maximum Scheduler Processing Time

Parameter	MAXPROCESSINGTIME
Description	Transaction timeout, in seconds, for each appointment booking processed by Scheduler. This parameter only applies to products that use the Scheduler.
Ordinality	Mandatory
Valid Values	1 - 2147483647 (Default: 5)
J2EE Web Application Server	WLS WAS WASND
Tier	MOB
Installation Mode	EMBED NATIVE

A.2.122 MINREQUESTS - Initial Scheduler Minimum Requests

Parameter	MINREQUESTS
Description	Initial request pool size for Scheduler. This parameter only applies to products that use the Scheduler.
Ordinality	Mandatory
Valid Values	1 - 2147483647 (Default: 1)
J2EE Web Application Server	WLS WAS WASND
Tier	MOB
Installation Mode	EMBED NATIVE

A.2.123 MOBILITY_APP_ONLY - Deploy Only Mobility Web Application

Parameter	MOBILITY_APP_ONLY
Description	Whether the mobile web application is the only deployment on the server. This allows for a distributed installation. This parameter only applies to products that use the Scheduler.
Ordinality	Mandatory
Valid Values	[true false]
J2EE Web Application Server	WLS WAS WASND
Tier	MOB
Installation Mode	EMBED NATIVE

A.2.124 MODULES - Names of Modules Installed

Parameter	MODULES
Description	Generated list of modules. This is generated by the product installer. This parameter is provided for backward compatibility as modules installed are now autogenerated from installation records.
Ordinality	Optional
Valid Values	List of product codes.
J2EE Web Application Server	WLS WAS WASND
Tier	WEB BAS IWS BATCH MOB
Installation Mode	EMBED NATIVE

A.2.125 NLS_LANG - NLS Language Setting

Parameter	NLS_LANG
Description	Globalization Language setting for the database.
Ordinality	Mandatory
Valid Values	Valid NLS_LANG. Default: AMERICA_AMERICAN. AL32UTF8
J2EE Web Application Server	WLS WAS WASND
Tier	BAS IWS BATCH DB
Installation Mode	EMBED NATIVE

A.2.126 NODEID - Scheduler Node Identifier

Parameter	NODEID
Description	Scheduler Node Identifier. This parameter is provided for backward compatibility. This parameter only applies to products using the Scheduler.
Ordinality	Optional
Valid Values	Valid Node Identifier
J2EE Web Application Server	WLS WAS WASND
Tier	MOB
Installation Mode	EMBED NATIVE

A.2.127 OIM_SPML_NAME_SPACE - OIM Default Namespace

Parameter	OIM_SPML_NAME_SPACE
Description	Default Namespace used for Oracle Identity Manager integration. This setting is only available if OPEN_SPML_ENABLED_ENV is true.
Ordinality	Optional
Valid Values	Valid SPML Namespace. Default: http://xmlns.oracle.com/OIM/provisioning
J2EE Web Application Server	WLS WAS WASND
Tier	BAS
Installation Mode	EMBED NATIVE

A.2.128 OIM_SPML_SOAP_DEBUG_SETTING - OIM Interface Debug

Parameter	OIM_SPML_SOAP_DEBUG_SETTING
Description	Enables or Disables debug mode to diagnose issues with the Oracle Identity Manager integration. This setting is only available if OPEN_SPML_ENABLED_ENV is true.
Ordinality	Optional
Valid Values	[true false]
J2EE Web Application Server	WLS WAS WASND
Tier	BAS
Installation Mode	EMBED NATIVE

A.2.129 OIM_SPML_SOAP_ELEMENT - OIM SOAP Element

Parameter	OIM_SPML_SOAP_ELEMENT
Description	Name of top level SOAP element used for Oracle Identity Manager interface. This is autogenerated. This setting is only available if OPEN_SPML_ENABLED_ENV is true.
Ordinality	Optional
Valid Values	Valid SOAP Element. Default: SOAPElement
J2EE Web Application Server	WLS WAS WASND
Tier	BAS
Installation Mode	EMBED NATIVE

A.2.130 OIM_SPML_UBER_SCHEMA_NAME - Name of OIM Interface Schema

Parameter	OIM_SPML_UBER_SCHEMA_NAME
Description	Name of schema used for Oracle Identity Manager interface. This is autogenerated. This setting is only available if OPEN_SPML_ENABLED_ENV is true.
Ordinality	Optional
Valid Values	Valid product Schema. Default: F1-IDMUser
J2EE Web Application Server	WLS WAS WASND
Tier	BAS
Installation Mode	EMBED NATIVE

A.2.131 **ONLINE_DISPLAY_HOME** - Location of Print Rendering Software

Parameter	ONLINE_DISPLAY_HOME
Description	Location of Print Rendering Software such as Oracle Documaker or Group 1 Doc 1.
Ordinality	Optional
Valid Values	Valid product location of the print rendering software
J2EE Web Application Server	WLS WAS WASND
Tier	BAS BATCH
Installation Mode	EMBED NATIVE

A.2.132 **ONS_JAR_DIR** - Location of Oracle Notification Service Libraries

Parameter	ONS_JAR_DIR
Description	Location of Oracle Notification Services Libraries used for RAC Fast Connection Failover support.
Ordinality	Optional
Valid Values	Valid location of <code>ons.jar</code> file. Usually <code>\$ORACLE_HOME/opmn/lib</code>
J2EE Web Application Server	WLS WAS WASND
Tier	BAS BATCH DB
Installation Mode	EMBED NATIVE

A.2.133 ONSCONFIG - ONS Configuration

Parameter	ONSCONFIG
Description	ONS configuration string used for RAC Fast Connection Failover support. For example: racnode1.my.com:4200, racnode2.my.com:4200
Ordinality	Optional
Valid Values	ONS configuration string without nodes= prefix.
J2EE Web Application Server	WLS WAS WASND
Tier	BAS BATCH DB
Installation Mode	EMBED NATIVE

A.2.134 OPEN_SPML_ENABLED_ENV - Whether OIM Interface Enabled

Parameter	OPEN_SPML_ENABLED_ENV
Description	Enable or Disable Oracle Identity Manager integration
Ordinality	Optional
Valid Values	[true false]
J2EE Web Application Server	WLS WAS WASND
Tier	BAS
Installation Mode	EMBED NATIVE

A.2.135 OPSYS - Operating System

Parameter	OPSYs
Description	Internal variable used for platform specific configurations to be implemented.
Ordinality	Mandatory
Valid Values	Generated Operating System String
J2EE Web Application Server	WLS WAS WASND
Tier	WEB BAS IWS XAI BATCH MOB
Installation Mode	EMBED NATIVE

A.2.136 ORACLE_CLIENT_HOME - Oracle Client Home

Parameter	ORACLE_CLIENT_HOME
Description	Location of Oracle Client Software or Oracle Home. This is used for ONS and/or the Perl runtime.
Ordinality	Mandatory
Valid Values	Location of Oracle Client Installation. If the Oracle Database software is installed on the same machine, then this can be ORACLE_HOME.
J2EE Web Application Server	WLS WAS WASND
Tier	WEB BAS IWS XAI BATCH MOB
Installation Mode	EMBED NATIVE

A.2.137 OSB_HOME - Oracle Service Bus Home

Parameter	OSB_HOME
Description	Location of Oracle Service Bus. This is used to deploy Oracle Service Bus content. This setting only applies to products with prebuilt Oracle Service Bus content. This is not used for Oracle Service Bus Adapters.
Ordinality	Optional
Valid Values	Location of Oracle Service Bus installation.
J2EE Web Application Server	WLS
Tier	BAS
Installation Mode	EMBED NATIVE

A.2.138 OSB_HOST - Oracle Service Bus Host Name

Parameter	OSB_HOST
Description	Host Name for Oracle Service Bus. This is used to deploy Oracle Service Bus content. This setting only applies to products with prebuilt Oracle Service Bus content. This is not used for Oracle Service Bus Adapters.
Ordinality	Optional
Valid Values	Host Name for Oracle Service Bus.
J2EE Web Application Server	WLS
Tier	BAS
Installation Mode	EMBED NATIVE

A.2.139 OSB_LOG_DIR - Default Location for Oracle Service Bus Logs

Parameter	OSB_LOG_DIR
Description	Logging Directory Oracle Service Bus. This is used to deploy Oracle Service Bus content. This setting only applies to products with prebuilt Oracle Service Bus content. This is not used for Oracle Service Bus Adapters.
Ordinality	Optional
Valid Values	Logging directory for Oracle Service Bus content deployment.
J2EE Web Application Server	WLS
Tier	BAS
Installation Mode	EMBED NATIVE

A.2.140 OSB_PASS_WLS - Password for Oracle Service Bus User

Parameter	OSB_PASS_WLS
Description	Encrypted password for OSB deployment user (OSB_USER). This is used to deploy Oracle Service Bus content. This setting only applies to products with prebuilt Oracle Service Bus content. This is not used for Oracle Service Bus Adapters.
Ordinality	Optional
Valid Values	Generated Password.
J2EE Web Application Server	WLS
Tier	BAS
Installation Mode	EMBED NATIVE

A.2.141 OSB_PORT_NUMBER - Oracle Service Bus Port Number

Parameter	OSB_PORT_NUMBER
Description	Port number allocated to Oracle Service Bus. This is used to deploy Oracle Service Bus content. This setting only applies to products with prebuilt Oracle Service Bus content. This is not used for Oracle Service Bus Adapters.
Ordinality	Optional
Valid Values	Valid Administration port to use for deployment of content.
J2EE Web Application Server	WLS
Tier	BAS
Installation Mode	EMBED NATIVE

A.2.142 OSB_USER - User Name for Oracle Service Bus

Parameter	OSB_USER
Description	Administration user used for OSB deployment user. This is used to deploy Oracle Service Bus content. This setting only applies to products with prebuilt Oracle Service Bus content. This is not used for Oracle Service Bus Adapters.
Ordinality	Optional
Valid Values	Valid Administration user to use for deployment of content.
J2EE Web Application Server	WLS
Tier	BAS
Installation Mode	EMBED NATIVE

A.2.143 PERLHOME - Location of PERL

Parameter	PERLHOME
Description	Generated location for Perl runtime. Generated from ORACLE_CLIENT_HOME.
Ordinality	Mandatory
Valid Values	Generated location for Perl.
J2EE Web Application Server	WLS WAS WASND
Tier	WEB BAS IWS XAI BATCH MOB
Installation Mode	EMBED NATIVE

A.2.144 SERVER_ROLES - Which Server Roles are Enabled

Parameter	SERVER_ROLES		
Description	Which server roles are enabled for this installation.		
Ordinality	Mandatory		
Valid Values	Install generated		
J2EE Web Application Server	WLS WAS WASND		
Tier	WEB IWS BATCH		
Installation Mode	EMBED NATIVE		

A.2.145 SERVER_ROLE_BATCH - Whether the Batch Server is Enabled in this Installation

Parameter	SERVER_ROLE_BATCH		
Description	Whether this installation is to be used for batch processing		
Ordinality	Mandatory		
Valid Values	Install generated with true or false		
J2EE Web Application Server	WLS WAS WASND		
Tier	BATCH		
Installation Mode	EMBED NATIVE		

A.2.146 SERVER_ROLE_INTEGRATION - Whether the IWS Server is Enabled in this Installation

Parameter	SERVER_ROLE_INTEGRATION		
Description	Whether this installation is to be used for integration (IWS)		
Ordinality	Mandatory		
Valid Values	Install generated with true or false		
J2EE Web Application Server	WLS WAS WASND		
Tier	IWS		
Installation Mode	EMBED NATIVE		

A.2.147 SERVER_ROLE_ONLINE - Whether the Online Server is Enabled in this Installation

Parameter	SERVER_ROLE_ONLINE		
Description	Whether this installation is to be used for online		
Ordinality	Mandatory		
Valid Values	Install generated with true or false		
J2EE Web Application Server	WLS WAS WASND		
Tier	WEB		
Installation Mode	EMBED NATIVE		

A.2.148 SOA_HOME - Location of Oracle SOA Suite

Parameter	SOA_HOME		
Description	Location of Oracle SOA Suite software. This is used to deploy Oracle SOA Suite content. This setting only applies to products with prebuilt Oracle SOA Suite content.		
Ordinality	Optional		
Valid Values	Valid location of Oracle SOA Suite.		
J2EE Web Application Server	WLS		
Tier	BAS		
Installation Mode	EMBED NATIVE		

A.2.149 SOA_HOST - Hostname for Oracle SOA Suite

Parameter	SOA_HOST		
Description	Hostname for Oracle SOA Suite software. This is used to deploy Oracle SOA Suite content. This setting only applies to products with prebuilt Oracle SOA Suite content.		
Ordinality	Optional		
Valid Values	Valid host name for Oracle SOA Suite.		
J2EE Web Application Server	WLS		
Tier	BAS		
Installation Mode	EMBED NATIVE		

A.2.150 SOA_PORT_NUMBER - Port Number for Oracle SOA Suite

Parameter	SOA_PORT_NUMBER
Description	Port Number for Oracle SOA Suite software. This is used to deploy Oracle SOA Suite content. This setting only applies to products with prebuilt Oracle SOA Suite content.
Ordinality	Optional
Valid Values	Valid port number for Oracle SOA Suite.
J2EE Web Application Server	WLS
Tier	BAS
Installation Mode	EMBED NATIVE

A.2.151 SPLADMIN - Administration UserID

Parameter	SPLADMIN
Description	Administration OS user used to install the software. Used by utilities to assign ownership and for deployment purposes.
Ordinality	Mandatory
Valid Values	Valid Administration Account.
J2EE Web Application Server	WLS WAS WASND
Tier	WEB BAS IWS XAI BATCH MOB
Installation Mode	EMBED NATIVE

A.2.152 SPLADMINGROUP - Administration Group

Parameter	SPLADMINGROUP					
Description	Administration OS group used to install the software. Used by utilities to assign ownership and for deployment purposes.					
Ordinality	Mandatory					
Valid Values	Valid Administration Group.					
J2EE Web Application Server	WLS WAS WASND					
Tier	WEB BAS IWS XAI BATCH MOB					
Installation Mode	EMBED NATIVE					

A.2.153 SPLApp - Name of Online WAR File

Parameter	SPLApp					
Description	Name of online WAR file used for building purposes					
Ordinality	Mandatory					
Valid Values	Valid WAR file name.					
J2EE Web Application Server	WLS WAS WASND					
Tier	WEB BAS XAI					
Installation Mode	EMBED NATIVE					

A.2.154 SPLDIR - Home Directory of Product

Parameter	SPLDIR					
Description	Home Location of product software. This value must match the corresponding entry in cistab.					
Ordinality	Mandatory					
Valid Values	Valid Location of software. Generated by installer.					
J2EE Web Application Server	WLS WAS WASND					
Tier	WEB BAS IWS XAI BATCH MOB					
Installation Mode	EMBED NATIVE					

A.2.155 SPLDIROUT - Location of Product Output

Parameter	SPLDIROUT					
Description	Home Location of product output. This value must match the corresponding entry in <code>cistab</code> .					
Ordinality	Mandatory					
Valid Values	Valid Location of output. Generated by installer.					
J2EE Web Application Server	WLS WAS WASND					
Tier	WEB BAS IWS XAI BATCH MOB					
Installation Mode	EMBED NATIVE					

A.2.156 SPLENVIRON - Environment Identifier

Parameter	SPLENVIRON					
Description	Home Location of product output. This value must match the corresponding entry in <code>cistab</code> .					
Ordinality	Mandatory					
Valid Values	Valid Location of output. Generated by installer.					
J2EE Web Application Server	WLS WAS WASND					
Tier	WEB BAS IWS XAI BATCH MOB					
Installation Mode	EMBED NATIVE					

A.2.157 SPLSERVICEAPP - Name of Business Application Server Application

Parameter	SPLSERVICEAPP					
Description	Default name of application which is deployed on Business Application Server					
Ordinality	Mandatory					
Valid Values	Valid Server Application Names					
J2EE Web Application Server	WLS WAS WASND					
Tier	BAS					
Installation Mode	EMBED NATIVE					

A.2.158 SPLWAS - J2EE Web Application Server Type

Parameter	SPLWAS
Description	J2EE Web Application Server to be used for product.
Ordinality	Mandatory
Valid Values	<p>The valid values are:</p> <p>WLS - Oracle WebLogic</p> <p>WAS - IBM WebSphere</p> <p>WASND - IBM WebSphere ND</p>
J2EE Web Application Server	WLS WAS WASND
Tier	WEB BAS IWS XAI MOB
Installation Mode	EMBED NATIVE

A.2.159 SPLWEBAPP – Name of Web Application Server Application

Parameter	SPLWEBAPP
Description	Default name of application which is deployed on Web Application Server
Ordinality	Mandatory for Oracle WebLogic implementations
Valid Values	Valid Server Application Names
J2EE Web Application Server	WLS
Tier	WEB XAI MOB
Installation Mode	EMBED NATIVE

A.2.160 STRIP_HTML_COMMENTS - Strip Out Comments in Code

Parameter	STRIP_HTML_COMMENTS
Description	Enable or Disable Stripping comments in generated code. By default, code is commented for ease of extension. If these comments represent a security issue for your site, then they can be stripped out at runtime (true).
Ordinality	Mandatory
Valid Values	[true false]
J2EE Web Application Server	WLS WAS WASND
Tier	BAS
Installation Mode	EMBED NATIVE

A.2.161 TIMEOUT - Mobile Connection Timeout

Parameter	TIMEOUT
Description	Connection timeout, in seconds, for Mobile component between handhelds and server.
Ordinality	Mandatory
Valid Values	Valid Timeout value. Refer to spl.mwm.abr.timeout for more details.
J2EE Web Application Server	WLS WAS WASND
Tier	MOB
Installation Mode	EMBED NATIVE

A.2.162 TOP_VERSION - Product Version

Parameter	TOP_VERSION
Description	Product Version identifier string used by utilities and upgrade scripts.
Ordinality	Mandatory
Valid Values	Generated by installer and should not be altered manually.
J2EE Web Application Server	WLS WAS WASND
Tier	WEB BAS IWS XAI BATCH MOB
Installation Mode	EMBED NATIVE

A.2.163 TOP_VERSION_NUM - High Level Product Version

Parameter	TOP_VERSION_NUM
Description	Product Version identifier number used by utilities and upgrade scripts.
Ordinality	Mandatory
Valid Values	Generated by installer and should not be altered manually.
J2EE Web Application Server	WLS WAS WASND
Tier	WEB BAS IWS XAI BATCH MOB
Installation Mode	EMBED NATIVE

A.2.164 TS_ALIAS - Trust Alias

Parameter	TS_ALIAS
Description	Trust Alias contained in trust store used by keytool. It is recommended to retain the default setting, unless an alternative is desired
Ordinality	Mandatory
Valid Values	Valid alias. Default: ouaf.system
J2EE Web Application Server	WLS WAS WASND
Tier	WEB BAS IWS BATCH MOB
Installation Mode	EMBED NATIVE

A.2.165 TS_ALIAS_KEYALG - Key Algorithm

Parameter	TS_ALIAS_KEYALG
Description	Trust Alias Algorithm used by trust store used by keytool.
Ordinality	Mandatory
Valid Values	Valid algorithm . Default: AES
J2EE Web Application Server	WLS WAS WASND
Tier	WEB BAS IWS BATCH MOB
Installation Mode	EMBED NATIVE

A.2.166 TS_ALIAS_KEYSIZE - Keysize

Parameter	TS_ALIAS_KEYSIZE
Description	Trust key size strength used by trust store used by keytool .
Ordinality	Mandatory
Valid Values	Valid keysize . Default: 128
J2EE Web Application Server	WLS WAS WASND
Tier	WEB BAS IWS BATCH MOB
Installation Mode	EMBED NATIVE

A.2.167 TS_HMAC_ALIAS - HMAC Key Alias

Parameter	TS_HMAC_ALIAS
Description	Trust HMAC Alias contained in trust store used by keytool .
Ordinality	It is recommended to retain the default setting, unless an alternative is desired.
Valid Values	Mandatory
J2EE Web Application Server	WLS WAS WASND
Tier	WEB BAS IWS BATCH MOB
Installation Mode	EMBED NATIVE

A.2.168 TS_HMAC_ALIAS_KEYALG - HMAC Key Algorithm

Parameter	TS_HMAC_ALIAS_KEYALG
Description	Key HMAC Alias Algorithm used by trust store used by keytool .
Ordinality	Mandatory
Valid Values	Valid algorithm . Default: HmacSHA256
J2EE Web Application Server	WLS WAS WASND
Tier	WEB BAS IWS BATCH MOB
Installation Mode	EMBED NATIVE

A.2.169 TS_HMAC_ALIAS_KEYSIZE - HMAC Keysize

Parameter	TS_HMAC_ALIAS_KEYSIZE
Description	HMAC Keysize strength used by trust store used by keytool .
Ordinality	Mandatory
Valid Values	Valid keysize . Default: 256
J2EE Web Application Server	WLS WAS WASND
Tier	WEB BAS IWS BATCH MOB
Installation Mode	EMBED NATIVE

A.2.170 TS_IMPORT_KEYSTORE_FOLDER - Import Folder for Trust Store

Parameter	TS_IMPORT_KEYSTORE_FOLDER
Description	Location to import a third party Trust Store File from.
Ordinality	Mandatory
Valid Values	Valid location for external trust store .
J2EE Web Application Server	WLS WAS WASND
Tier	WEB BAS IWS BATCH MOB
Installation Mode	EMBED NATIVE

A.2.171 TS_KEYSTORE_FILE - Trust Store File Name

Parameter	TS_KEYSTORE_FILE
Description	Trust Store File used by keytool .
Ordinality	Mandatory
Valid Values	Valid location and file name for trust store . Linux: \$SPLEBASE/ks/.ouaf_truststore Windows: %SPLEBASE%\ks\ouaf_truststore
J2EE Web Application Server	WLS WAS WASND
Tier	WEB BAS IWS BATCH MOB
Installation Mode	EMBED NATIVE

A.2.172 TS_MODE - Key Padding Mode

Parameter	TS_MODE
Description	Key Padding Mode
Ordinality	Mandatory
Valid Values	Valid Padding for Trust store. Default: CBC
J2EE Web Application Server	WLS WAS WASND
Tier	WEB BAS IWS BATCH MOB
Installation Mode	EMBED NATIVE

A.2.173 TS_PADDING - Key Padding Algorithm

Parameter	TS_PADDING
Description	Key Padding Algorithm used for key generation
Ordinality	Mandatory
Valid Values	Valid Padding Algorithm for Trust store. Default: PKCS5Padding
J2EE Web Application Server	WLS WAS WASND
Tier	WEB BAS IWS BATCH MOB
Installation Mode	EMBED NATIVE

A.2.174 TS_STOREPASS_FILE - Key Password Store Pass

Parameter	TS_STOREPASS_FILE
Description	Password Trust store File used by keytool .
Ordinality	Mandatory
Valid Values	Valid location and file name for trust store . Linux: \$SPLBASE/ks/.ouaf_truststorepass Windows: %SPLBASE%\ks\ouaf_truststorepass
J2EE Web Application Server	WLS WAS WASND
Tier	WEB BAS IWS BATCH MOB
Installation Mode	EMBED NATIVE

A.2.175 TS_STORETYPE - Key Store Type

Parameter	TS_STORETYPE
Description	Trust Store Type used by keytool .
Ordinality	Mandatory
Valid Values	Valid Key Store Type . Default: JCEKS
J2EE Web Application Server	WLS WAS WASND
Tier	WEB BAS IWS BATCH MOB
Installation Mode	EMBED NATIVE

A.2.176 URL - Mobile JNDI URL

Parameter	URL
Description	Connection URL, for Mobile component.
Ordinality	Mandatory
Valid Values	Valid URL. Refer to spl.mwm.abr.url for more details.
J2EE Web Application Server	WLS WAS WASND
Tier	MOB
Installation Mode	EMBED NATIVE

A.2.177 WAS_HOME - IBM WebSphere Home

Parameter	WAS_HOME
Description	Location of IBM WebSphere software for deployment purposes. This setting is only applicable to IBM WebSphere customers.
Ordinality	Mandatory
Valid Values	Location of IBM WebSphere installation
J2EE Web Application Server	WAS
Tier	WEB BAS IWS XAI MOB
Installation Mode	NATIVE

A.2.178 WAS_PASSWORD - IBM WebSphere Administration Password

Parameter	WAS_PASSWORD
Description	Encrypted password for administration user for IBM WebSphere/IBM WebSphere ND. This setting is only applicable to IBM WebSphere and IBM WebSphere ND customers.
Ordinality	Mandatory
Valid Values	Encrypted password for administration user.
J2EE Web Application Server	WAS WASND
Tier	WEB BAS IWS XAI MOB
Installation Mode	NATIVE

A.2.179 WAS_USERID - IBM WebSphere Administration User

Parameter	WAS_USERID
Description	Administration user for IBM WebSphere/IBM WebSphere ND. This setting is only applicable to IBM WebSphere and IBM WebSphere ND customers.
Ordinality	Mandatory
Valid Values	Administration user.
J2EE Web Application Server	WAS WASND
Tier	WEB BAS IWS XAI MOB
Installation Mode	NATIVE

A.2.180 WASND_DMGR_HOST - IBM WebSphere Deployment Manager Host Name

Parameter	WASND_DMGR_HOST
Description	Location of IBM WebSphere ND host for deployment purposes. This setting is only applicable to IBM WebSphere ND customers.
Ordinality	Mandatory
Valid Values	Host of IBM WebSphere ND Deployment Manager
J2EE Web Application Server	WASND
Tier	WEB BAS IWS XAI MOB
Installation Mode	NATIVE

A.2.181 WASND_HOME - IBM WebSphere ND Home

Parameter	WASND_HOME
Description	Location of IBM WebSphere ND software for deployment purposes. This setting is only applicable to IBM WebSphere ND customers.
Ordinality	Mandatory
Valid Values	Location of IBM WebSphere ND installation
J2EE Web Application Server	WASND
Tier	WEB BAS IWS XAI MOB
Installation Mode	NATIVE

A.2.182 WEBSERVICES_ENABLED - Whether Inbound Web Services is Enabled

Parameter	WEBSERVICES_ENABLED
Description	Enable or Disable Inbound Web Services support
Ordinality	Mandatory
Valid Values	[true false]
J2EE Web Application Server	WLS WAS WASND
Tier	IWS
Installation Mode	EMBED NATIVE

A.2.183 WEB_ADDITIONAL_OPT - Additional Java Options for Web

Parameter	WEB_ADDITIONAL_OPT
Description	Additional Java Options for Web Application Server. For native installations, these options can be set on the Server definition.
Ordinality	Optional
Valid Values	Valid java options for JVM used.
J2EE Web Application Server	WLS WAS WASND
Tier	WEB BAS IWS XAI MOB
Installation Mode	EMBED

A.2.184 WEB_APP - Name of WebSphere Server Application

Parameter	WEB_APP
Description	Default Name for WebSphere Server Application
Ordinality	Mandatory for WebSphere implementations
Valid Values	Valid Server Application Names
J2EE Web Application Server	WAS WASND
Tier	WEB XAI MOB
Installation Mode	EMBED NATIVE

A.2.185 WEB_APPVIEWER_FORM_LOGIN_ERROR_PAGE - AppViewer Form Login Error Page

Parameter	WEB_APPVIEWER_FORM_LOGIN_ERROR_PAGE
Description	Error Page used for invalid AppViewer Login.
Ordinality	Mandatory
Valid Values	Valid JSP for error pages
J2EE Web Application Server	WLS WAS WASND
Tier	WEB
Installation Mode	EMBED NATIVE

A.2.186 WEB_APPVIEWER_FORM_LOGIN_PAGE - AppViewer Form Login Page

Parameter	WEB_APPVIEWER_FORM_LOGIN_PAGE
Description	Login Page used for AppViewer Login.
Ordinality	Mandatory
Valid Values	Valid JSP for login
J2EE Web Application Server	WLS WAS WASND
Tier	WEB
Installation Mode	EMBED NATIVE

A.2.187 WEB_APPVIEWER_PRINCIPAL_NAME - Application Viewer Principal Name

Parameter	WEB_APPVIEWER_PRINCIPAL_NAME
Description	Principal Name for AppViewer
Ordinality	Mandatory
Valid Values	Valid Principal Name
J2EE Web Application Server	WLS WAS WASND
Tier	WEB
Installation Mode	EMBED NATIVE

A.2.188 WEB_APPVIEWER_ROLE_NAME - Application Viewer Security Role

Parameter	WEB_APPVIEWER_ROLE_NAME
Description	Role Name for AppViewer
Ordinality	Mandatory
Valid Values	Valid Role Name
J2EE Web Application Server	WLS WAS WASND
Tier	WEB
Installation Mode	EMBED NATIVE

A.2.189 WEB_BATCH_CLUSTER_URL - Batch Cluster URL

Parameter	WEB_BATCH_CLUSTER_URL
Description	Batch Cluster URL for online submission tracking of Mobile application
Ordinality	Mandatory
Valid Values	Valid Role Name
J2EE Web Application Server	WLS WAS WASND
Tier	MOB
Installation Mode	EMBED NATIVE

A.2.190 WEB_CONTEXT_ROOT - Web Context Root

Parameter	WEB_CONTEXT_ROOT
Description	Web Context for product
Ordinality	Mandatory
Valid Values	Valid context. Default: spl
J2EE Web Application Server	WLS WAS WASND
Tier	WEB BAS IWS XAI MOB
Installation Mode	EMBED NATIVE

A.2.191 WEB_DEPLOY_APPVIEWER – Deploy AppViewer or Not

Parameter	WEB_DEPLOY_APPVIEWER
Description	Whether the AppViewer application is included in the online EAR file. A value of true adds the appViewer to the online EAR file. A value of false does not add the appViewer content to the online EAR file.
	Note: If the appViewer is not deployed the online administration functions that use the appViewer will not display this content.
	It is recommended to set this value to false for non-development environments.
Ordinality	Mandatory
Valid Values	[true false]

J2EE Web Application Server	WLS	WAS	WASND
Tier	WEB		
Installation Mode	EMBED	NATIVE	

A.2.192 WEB_DEPLOY_EAR - Deploy EAR File

Parameter	WEB_DEPLOY_EAR
Description	Whether the EAR file is built and deployed or not for development environments. It is recommended to set this value to true for non-development environments. This setting replace components of the WEB_ISDEVELOPMENT variable to allow development platforms to use expanded or EAR mode independently.
Ordinality	Mandatory
Valid Values	[true false]
J2EE Web Application Server	WLS
Tier	WEB
Installation Mode	EMBED

A.2.193 WEB_ENABLE_HEALTHCHECK - Enable System Healthcheck

Parameter	WEB_ENABLE_HEALTHCHECK
Description	Enable the system healthcheck function used by the Oracle Application Management Pack for Oracle Utilities available from Oracle Enterprise Manager.
Ordinality	Mandatory
Valid Values	[true false]
J2EE Web Application Server	WLS
Tier	WEB
Installation Mode	EMBED NATIVE

A.2.194 WEB_FORM_LOGIN_ERROR_PAGE - Default Form Login Error Page

Parameter	WEB_FORM_LOGIN_ERROR_PAGE
Description	Error Page used for invalid online Login.
Ordinality	Mandatory
Valid Values	Valid JSP for error pages
J2EE Web Application Server	WLS WAS WASND
Tier	WEB
Installation Mode	EMBED NATIVE

A.2.195 WEB_FORM_LOGIN_PAGE - Default Form Login Page

Parameter	WEB_FORM_LOGINPAGE
Description	Login Page used for online Login.
Ordinality	Mandatory
Valid Values	Valid JSP for login
J2EE Web Application Server	WLS WAS WASND
Tier	WEB
Installation Mode	EMBED NATIVE

Note:

If WEB_HELP_FORM_LOGIN_ERROR_PAGE and/or WEB_APPVIEWER_FORM_LOGIN_ERROR_PAGE are not specified then they default to the value specified in WEB_FORM_LOGIN_ERROR_PAGE.

If WEB_HELP_FORM_LOGIN_PAGE and/or WEB_APPVIEWER_FORM_LOGIN_PAGE are not specified then they default to the value specified in WEB_FORM_LOGIN_PAGE.

If WEB_APPVIEWER_ROLE_NAME and/or WEB_APPVIEWER_PRINCIPAL_NAME are not specified they are default to WEB_ROLE_NAME and WEB_PRINCIPAL_NAME respectively.

A.2.196 WEB_HELP_FORM_LOGIN_ERROR_PAGE - Help Form Login Error Page

Parameter	WEB_HELP_FORM_LOGIN_ERROR_PAGE
Description	Error Page used for invalid Help Login.
Ordinality	Mandatory
Valid Values	Valid JSP for error pages
J2EE Web Application Server	WLS WAS WASND
Tier	WEB
Installation Mode	EMBED NATIVE

A.2.197 WEB_HELP_FORM_LOGIN_PAGE - Help Form Login Page

Parameter	WEB_HELP_FORM_LOGIN_PAGE
Description	Login Page used for Help Login.
Ordinality	Mandatory
Valid Values	Valid JSP for login
J2EE Web Application Server	WLS WAS WASND
Tier	WEB
Installation Mode	EMBED NATIVE

A.2.198 WEB_ISAPPVIEWER - Enable AppViewer

Parameter	WEB_ISAPPVIEWER
Description	Enable or Disable AppViewer from deployment. The use of AppViewer is recommended for appropriate non- production environments only.
Ordinality	Mandatory
Valid Values	[true false]
J2EE Web Application Server	WLS WAS WASND
Tier	WEB
Installation Mode	EMBED NATIVE

A.2.199 WEB_ISDEVELOPMENT - Development Environment

Parameter	WEB_ISDEVELOPMENT
Description	Enable or Disable Development on this product environment. This setting assumes that the Oracle Utilities SDK.
Ordinality	Mandatory
Valid Values	[true false]
J2EE Web Application Server	WLS WAS WASND
Tier	WEB BAS IWS XAI BATCH MOB
Installation Mode	EMBED NATIVE

A.2.200 WEB_IWS_MDB_RUNAS_USER - Default User for MDB to Run as within Product

Parameter	WEB_IWS_MDB_RUNAS_USER
Description	The default product user the MDB uses to run its interface. This value is used if no JMS credentials are provided on the message header. A blank value, the default, for this parameter disables the function and assumes all JMS messages will include their credentials in the head of the message.
Ordinality	Optional
Valid Values	Blank (not enabled) or a valid product authorization userID (not login id)
J2EE Web Application Server	WLS WAS WASND
Tier	IWS
Installation Mode	EMBED NATIVE

A.2.201 WEB_IWS_SUPER_USERS - Users to Run as in IWS

Parameter	WEB_IWS_SUPER_USERS
Description	Default product user used for authorization for Inbound Web Services. This value is used for internal calls used for Inbound Web Services.
Ordinality	Optional
Valid Values	Blank (not enabled) or a valid product authorization userID (not login id)
J2EE Web Application Server	WLS WAS WASND
Tier	WEB
Installation Mode	EMBED NATIVE

A.2.202 WEB_JMX_RMI_PORT_PERFORMANCE - JMX Port for Web Application Server Monitoring

Parameter	WEB_JMX_RMI_PORT_PERFORMANCE
Description	Port number for JMX monitoring for Online monitoring.
Ordinality	Mandatory
Valid Values	Valid open port number for monitoring.
J2EE Web Application Server	WLS WAS WASND
Tier	WEB
Installation Mode	EMBED NATIVE

A.2.203 WEB_L2_CACHE_MODE - Turn Off L2 Cache for Online Submission

Parameter	WEB_L2_CACHE_MODE
Description	Enables (on) or disables (off) Level 2 cache for online submission. Used for development purposes where online submission cache is off. Note: Some batch processes require L2 Cache to be disabled. Refer to individual job documentation for details.
Ordinality	Mandatory
Valid Values	[on off]
J2EE Web Application Server	WLS WAS WASND
Tier	WEB BATCH
Installation Mode	EMBED NATIVE

A.2.204 WEB_MAXAGE - Text Cache

Parameter	WEB_MAXAGE
Description	Set the duration (in seconds) to store page structures from the product, in the client cache, on the client browser.
Ordinality	Mandatory
Valid Values	See maxAge for valid values.
J2EE Web Application Server	WLS WAS WASND
Tier	WEB
Installation Mode	EMBED NATIVE

A.2.205 WEB_MAXAGEI - Image Cache

Parameter	WEB_MAXAGEI
Description	Set the duration (in seconds) to store images, in the client cache, from the product on the client browser.
Ordinality	Mandatory
Valid Values	See maxAgeI for valid values.
J2EE Web Application Server	WLS WAS WASND
Tier	WEB
Installation Mode	EMBED NATIVE

A.2.206 WEB_MEMORY_OPT_MAX - Maximum Web Application Server JVM Memory

Parameter	WEB_MEMORY_OPT_MAX
Description	Maximum Web Application Server JVM Memory in MB. Corresponds to Xmx java option. In native mode implementations, this setting is set on the Server definition.
Ordinality	Optional
Valid Values	Valid Memory setting (in MB). Default: 1024
J2EE Web Application Server	WLS WAS WASND
Tier	WEB
Installation Mode	EMBED

A.2.207 WEB_MEMORY_OPT_MAXPERMSIZE - Web Application Server JVM Max PermGen Size

Parameter	WEB_MEMORY_OPT_MAXPERMSIZE
Description	Maximum Web Application Server JVM PermGen Memory in MB. Corresponds to XX:PermSize java option. This option does not apply to Oracle JRockit implementations. In native mode implementations, this setting is set on the Server definition.
Ordinality	Optional
Valid Values	Valid Memory setting (in MB). Default: 500
J2EE Web Application Server	WLS WAS WASND
Tier	WEB
Installation Mode	EMBED

A.2.208 WEB_MEMORY_OPT_MIN - Initial Web Application Server JVM Memory

Parameter	WEB_MEMORY_OPT_MIN
Description	Initial Web Application Server JVM Memory in MB. Corresponds to Xms java option. In native mode implementations, this setting is set on the Server definition.
Ordinality	Optional
Valid Values	Valid Memory setting (in MB). Default: 1024
J2EE Web Application Server	WLS WAS WASND
Tier	WEB
Installation Mode	EMBED

A.2.209 WEB_NODENAME - IBM WebSphere ND Node Name

Parameter	WEB_NODENAME
Description	Node Name for IBM WebSphere ND.
Ordinality	Mandatory
Valid Values	Valid IBM WebSphere ND node name
J2EE Web Application Server	WASND
Tier	WEB BAS IWS XAI MOB
Installation Mode	EMBED NATIVE

A.2.210 WEB_PRELOADALL - Preload All Pages on Startup

Parameter	WEB_PRELOADALL
Description	Enable or Disable preload of pages at startup. This determines the scope of any reload. A value of false (default) only preloads the Main menu only. A value of true preloads all functions on all menus. A value of true will lengthen the startup process.
Ordinality	Mandatory
Valid Values	[true false]
J2EE Web Application Server	WLS WAS WASND
Tier	WEB
Installation Mode	EMBED NATIVE

A.2.211 WEB_PRINCIPAL_NAME - Default J2EE Authorization Principal

Parameter	WEB_PRINCIPAL_NAME
Description	Principal Name for online application.
Ordinality	Mandatory
Valid Values	Valid Principal Name. Default: cisusers
J2EE Web Application Server	WLS WAS WASND
Tier	WEB BAS IWS XAI
Installation Mode	EMBED NATIVE

A.2.212 WEB_ROLE_NAME - Default J2EE Authorization Role

Parameter	WEB_ROLE_NAME
Description	Role Name for online application
Ordinality	Mandatory
Valid Values	Valid Role Name. Default: cisusers
J2EE Web Application Server	WLS WAS WASND
Tier	WEB BAS IWS XAI
Installation Mode	EMBED NATIVE

A.2.213 WEB_SERVER_HOME - Location of Web Application Server

Parameter	WEB_SERVER_HOME
Description	Generic location of Web Application Server. This value is then used to set the following values: WAS_HOME - IBM WebSphere WASND_HOME - IBM WebSphere ND WL_HOME - Oracle WebLogic
Ordinality	Mandatory
Valid Values	Home location of Web Application Server software
J2EE Web Application Server	WLS WAS WASND
Tier	WEB BAS IWS XAI
Installation Mode	EMBED NATIVE

A.2.214 WEB_SERVER_VERSION - Web Server Version

Parameter	WEB_SERVER_VERSION
Description	Full Version of J2EE Web Application Server. Used for utilities to ensure correct templates are used.
Ordinality	Mandatory
Valid Values	Generated by installer
J2EE Web Application Server	WLS WAS WASND
Tier	WEB BAS IWS XAI
Installation Mode	EMBED NATIVE

A.2.215 WEB_SERVER_VERSION_MAIN

Parameter	WEB_SERVER_VERSION_MAIN
Description	Substring Version of J2EE Web Application Server. Used for utilities to ensure correct templates are used
Ordinality	Mandatory
Valid Values	Generated by installer
J2EE Web Application Server	WLS WAS WASND
Tier	WEB BAS IWS XAI
Installation Mode	EMBED NATIVE

A.2.216 WEB_SPLPASS - Application Administration Password

Parameter	WEB_SPLPASS
Description	Encrypted password for administration user for Oracle WebLogic. This setting is only applicable to Oracle WebLogic customers and is only used for embedded mode installations.
Ordinality	Mandatory
Valid Values	Encrypted password for administration user.
J2EE Web Application Server	WLS
Tier	WEB BAS IWS XAI MOB
Installation Mode	EMBED

A.2.217 WEB_SPLUSER - Application Administration UserID

Parameter	WEB_SPLUSER
Description	Administration user for Oracle WebLogic. This setting is only applicable to Oracle WebLogic customers and is only used for embedded mode installations.
Ordinality	Mandatory
Valid Values	Administration user. Default: system
J2EE Web Application Server	WLS
Tier	WEB BAS IWS XAI MOB
Installation Mode	EMBED

A.2.218 WEB_SVRNAME - IBM WebSphere Server Name

Parameter	WEB_SVRNAME
Description	Server Name for IBM WebSphere/IBM WebSphere ND.
Ordinality	Mandatory
Valid Values	Valid IBM WebSphere/IBM WebSphere ND server name
J2EE Web Application Server	WAS WASND
Tier	WEB BAS IWS XAI MOB
Installation Mode	EMBED NATIVE

A.2.219 WEB_WASPASS - IBM WebSphere JNDI Password

Parameter	WEB_WASPASS
Description	Encrypted password for JNDI user for IBM WebSphere/IBM WebSphere ND. This setting is only applicable to IBM WebSphere/IBM WebSphere ND customers.
Ordinality	Mandatory
Valid Values	Encrypted password for JNDI user.
J2EE Web Application Server	WAS WASND
Tier	WEB BAS IWS XAI MOB
Installation Mode	EMBED

A.2.220 WEB_WASUSER - IBM WebSphere JNDI UserID

Parameter	WEB_WASUSER
Description	Administration JNDI user for IBM WebSphere/IBM WebSphere ND. This parameter is used for any JNDI calls to the servers. This setting is only applicable to IBM WebSphere/IBM WebSphere ND customers.
Ordinality	Mandatory
Valid Values	JNDI Administration User.
J2EE Web Application Server	WAS WASND
Tier	WEB BAS IWS XAI MOB
Installation Mode	EMBED

A.2.221 WEB_WLAUTHMETHOD - Authentication Method

Parameter	WEB_WLAUTHMETHOD
Description	J2EE Authorization Method implemented.
Ordinality	Mandatory
Valid Values	Valid values: FORM (Default) - Use login forms BASIC - Use Operating System Login CLIENT-CERT - Client Certificate
J2EE Web Application Server	WLS WAS WASND
Tier	WEB BAS IWS XAI MOB
Installation Mode	EMBED NATIVE

A.2.222 WEB_WLHOST - Web Server Host

Parameter	WEB_WLHOST
Description	Host Name for Oracle WebLogic Install. This is used for Oracle WebLogic customers only and embedded installations only.
Ordinality	Mandatory
Valid Values	Valid Host Name. Default: localhost
J2EE Web Application Server	WLS
Tier	WEB BAS IWS XAI MOB
Installation Mode	EMBED

A.2.223 WEB_WLPAGECHECKSECONDS - Interval for Recompilation of JSP

Parameter	WEB_WLPAGECHECKSECONDS
Description	Interval, in seconds, to force recompilation for server JSP's. This is used for Oracle WebLogic customers only. This setting is designed to be altered for development environments. The default is recommended for all other environments.
Ordinality	Mandatory
Valid Values	Valid Recompile time. Default: 43200
J2EE Web Application Server	WLS
Tier	WEB
Installation Mode	EMBED NATIVE

A.2.224 WEB_WLPORT - Web Server HTTP Port

Parameter	WEB_WLPORT
Description	Port number for environment for online system.
Ordinality	Mandatory
Valid Values	Valid open port number. Default: 6500
J2EE Web Application Server	WLS
Tier	WEB
Installation Mode	EMBED NATIVE

A.2.225 WEB_WLSSLPORT - Oracle WebLogic SSL HTTP Port

Parameter	WEB_WLSSLPORT
Description	SSL Port number for environment for online system.
Ordinality	Mandatory
Valid Values	Valid open port number. Default: 6501
J2EE Web Application Server	WLS
Tier	WEB
Installation Mode	EMBED NATIVE

A.2.226 WEB_WLSSYSPASS - Oracle WebLogic JNDI System Password

Parameter	WEB_WLSSYSPASS
Description	Encrypted Oracle WebLogic JNDI Password used for JNDI lookups. This is used for Oracle WebLogic customers only.
Ordinality	Mandatory
Valid Values	Valid JNDI Password.
J2EE Web Application Server	WLS
Tier	WEB
Installation Mode	EMBED NATIVE

A.2.227 WEB_WLSYSUSER - Oracle WebLogic JNDI System UserID

Parameter	WEB_WLSYSUSER
Description	Oracle WebLogic JNDI User used for JNDI lookups. This is used for Oracle WebLogic customers only.
Ordinality	Mandatory
Valid Values	Valid JNDI User.
J2EE Web Application Server	WLS
Tier	WEB
Installation Mode	EMBED NATIVE

A.2.228 WEB_WLS_SVRNAME - Oracle WebLogic Server Name

Parameter	WEB_WLS_SVRNAME
Description	Oracle WebLogic Server Name. This is used for Oracle WebLogic customers only and embedded installations only.
Ordinality	Mandatory
Valid Values	Valid Server Name. Default: myserver
J2EE Web Application Server	WLS
Tier	WEB
Installation Mode	EMBED

A.2.229 WLS_ADMIN_PORT - Admin Console Port Number

Parameter	WLS_ADMIN_PORT
Description	Oracle WebLogic Administration Port. Only supplied if Administration port differs from application port. Oracle WebLogic Server Name. This is used for Oracle WebLogic customers only and embedded installations only.
Ordinality	Mandatory
Valid Values	Valid Port Number. Default: Value of WEB_WLPORT.
J2EE Web Application Server	WLS
Tier	WEB
Installation Mode	EMBED

A.2.230 WLS_CLUSTER_NAME - Name of Cluster for Product

Parameter	WLS_CLUSTER_NAME
Description	Oracle WebLogic Cluster Name for clustered environments. This value must be set for customers using the Application Management Pack for Oracle Utilities to link the cluster target with the product.
Ordinality	Optional
Valid Values	Valid Cluster Name.
J2EE Web Application Server	WLS
Tier	WEB
Installation Mode	EMBED NATIVE

A.2.231 WLS_DIAGNOSTIC_BUILT_IN_MODULE - Diagnostic Module Name

Parameter	WLS_DIAGNOSTIC_BUILT_IN_MODULE
Description	Name of Diagnostics Module used for diagnostics rules if WLS_DIAGNOSTIC_CONTEXT_ENABLED is set to true.
Ordinality	Optional
Valid Values	Valid Diagnostics Module name. Default: None
J2EE Web Application Server	WLS

Tier	WEB
Installation Mode	EMBED

A.2.232 WLS_DIAGNOSTIC_CONTEXT_ENABLED - ECID Support

Parameter	WLS_DIAGNOSTIC_CONTEXT_ENABLED
Description	This enables (true) or disables (false) ECID Support.
Ordinality	Optional
Valid Values	{true false}.
J2EE Web Application Server	WLS
Tier	WEB
Installation Mode	EMBED

A.2.233 WLS_DIAGNOSTIC_VOLUME- Diagnostic Volume

Parameter	WLS_DIAGNOSTIC_VOLUME
Description	This sets the diagnostic volume used by Oracle diagnostic tools if WLS_DIAGNOSTIC_CONTEXT_ENABLED is set to true.
Ordinality	Optional
Valid Values	{Off Low Medium High}. Refer to the Oracle WebLogic online help for a description of the values.
J2EE Web Application Server	WLS
Tier	WEB
Installation Mode	EMBED

A.2.234 WLS_DOMAIN_HOME - Oracle WebLogic Domain Home

Parameter	WLS_DOMAIN_HOME
Description	Domain Home directory for installation. Used if installation has multiple domains installed
Ordinality	Mandatory
Valid Values	Valid Domain Home

J2EE Web Application Server	WLS
Tier	WEB
Installation Mode	EMBED

A.2.235 WLS_OVERRIDE_PROTECT - Override Protection

Parameter	WLS_OVERRIDE_PROTECT
Description	Sets Overload Protection setting in Oracle WebLogic
Ordinality	Mandatory
Valid Values	Valid Panic Action settings for Overload (system-exit or no-action). Default: system-exit ²⁹
J2EE Web Application Server	WLS
Tier	WEB
Installation Mode	EMBED

A.2.236 WLS_WEB_WLSYSPASS - Console Password for Oracle WebLogic

Parameter	WLS_WEB_WLSYSPASS
Description	Encrypted Oracle WebLogic Password used for console. This is used for Oracle WebLogic customers only and embedded installations only.
Ordinality	Mandatory
Valid Values	Valid console Password.
J2EE Web Application Server	WLS
Tier	WEB
Installation Mode	EMBED

²⁹ system-exit will force out overload users. They will receive an appropriate error.

A.2.237 WLS_WEB_WLSYSUSER - Console User for Oracle WebLogic

Parameter	WLS_WEB_WLSYSUSER
Description	Encrypted Oracle WebLogic user used for console. This is used for Oracle WebLogic customers only and embedded installations only.
Ordinality	Mandatory
Valid Values	Valid console user. Default: system
J2EE Web Application Server	WLS
Tier	WEB
Installation Mode	EMBED

A.2.238 WLTHININT3CLIENT_JAR_DIR - Location of Thin WebLogic T3 Client

Parameter	WLTHININT3CLIENT_JAR_DIR
Description	Location of Oracle WebLogic thin Client for JMX and other interfaces. Used for integration to Oracle products for monitoring.
Ordinality	Optional
Valid Values	Valid location of wlthint3client.jar
J2EE Web Application Server	WLS
Tier	IWS WEB
Installation Mode	EMBED

A.2.239 WL_HOME - Oracle WebLogic Home

Parameter	WL_HOME
Description	Home directory of Oracle WebLogic. This is used for Oracle WebLogic customers only and embedded installations only.
Ordinality	Mandatory
Valid Values	Valid console user. Default: system
J2EE Web Application Server	WLS
Tier	WEB
Installation Mode	EMBED

A.2.240 XAIApp - Name of XAI WAR File

Parameter	XAIApp
Description	Name of XAI WAR file as generated for builds. This is generated and should not be changed.
Ordinality	Mandatory
Valid Values	Valid WAR file name. Default: XAIApp.war
J2EE Web Application Server	WLS WAS WASND
Tier	XAI
Installation Mode	EMBED NATIVE

A.2.241 XAI_DBPASS - Password for Database User for XAI

Parameter	XAI_DBPASS		
Description	Encrypted database user password for the XAI component of the product.		
Ordinality	Mandatory		
Valid Values	Encrypted Password		
J2EE Web Application Server	WLS	WAS	WASND
Tier	XAI	DB	
Installation Mode	EMBED	NATIVE	

A.2.242 XAI_DBUSER - Database User Used for XAI

Parameter	XAI_DBUSER		
Description	Database User, with Read/Write permissions used for pooled connections for XAI transactions.		
Ordinality	Mandatory		
Valid Values	Valid Database User used in installation		
J2EE Web Application Server	WLS	WAS	WASND
Tier	XAI	DB	
Installation Mode	EMBED	NATIVE	

A.2.243 XQUERIES_TO_CACHE - Size of XQuery Cache

Parameter	XQUERIES_TO_CACHE		
Description	Size of XQuery/XPath Cache in number of queries. Increasing the cache size may increase memory requirements for the product. This sets the value of com.oracle.XPath.LRUSize in the spl.properties file		
Ordinality	Optional		
Valid Values	Defaults from templates (-1 - Unlimited in size)		
J2EE Web Application Server	WLS	WAS	WASND
Tier	BAS	BATCH	IWS
Installation Mode	EMBED	NATIVE	

A.2.244 XQUERY_CACHE_FLUSH_TIMEOUT - Cache Life for XQueries

Parameter	XQUERY_CACHE_FLUSH_TIMEOUT
Description	Length of time in seconds that XQuery and XPath queries are cached and set the value of com.oracle.XPath.flushTimeout in the spl.properties file.
Ordinality	Optional
Valid Values	Defaults from templates (0 - Never flush is the default)
J2EE Web Application Server	WLS WAS WASND
Tier	BAS BATCH IWS MOB
Installation Mode	EMBED NATIVE

A.3 Web.xml

The Web deployment descriptor editor lets you specify deployment information for modules created in the Web development environment. The information appears in the web.xml file. The web.xml file for a Web project provides information necessary for deploying a Web application module. It is used in building a WAR/EAR file from a project.

The online and web Services J2EE applications for the product are controlled by this configuration file which holds the behavioral configuration for the applications. Refer to <http://jcp.org/en/jsr/detail?id=109> for more details of the XML format.

The following sections outline the specific settings for the product.

A.3.1 Filter Mappings - J2EE Filters

Note: Filters should not be altered unless instructed by Oracle Support. Refer to the web.xml file for the relevant settings.

The following filters apply to the product:

Filter	Usage
Browser Cache Filter	Browser Client side caching settings - Used with MaxAge .
CSS Stylesheet Direction Filter	CSS Filter
Doctype Replace Filter	JDOC Filter
FlushAll Redirect Filter	Cache management utility Filter
GZip Compression Filter	HTTP 1.1 compression filter
Header Security Filter	OWASP processing of HTTP headers using SAMEORIGIN
HTML Comment stripping Filter	Removal of comments from HTTP transmission
Image Browser Cache Filter	Browser Client side caching settings for image files - Used with MaxAge1.
Image RTL Filter	Right to Left support Filter
Javascript Comment stripping Filter	Removal of comments from javascript transmission
Minification Filter	Optimization code
Privacy Page Redirect Filter	Privacy page redirect to /cm/privacy.html
Request Context Filter	Generic context Filter
Rest Security Filter	REST security support
Security Filter	Generic security filter to delegate security to J2EE container
Timezone Database ContentType Filter	Time zone support

A.3.2 disableCompression - Disable Compression

Parameter	disableCompression
Description	Enables or disables compression between the Web Application Server and Business Application Server (true or false).
Ordinality	Mandatory
Valid Values	[true false]
Source	Derived from WEB_ISDEVELOPMENT parameter from ENVIRON.INI. It is highly recommended to set to false for all environment exception is development environments using Oracle Utilities SDK.
Applicability	WEB
Example	<pre><context-param> <param-name>disableCompression</param-name> <param-value>false</param-value> </context-param></pre>

A.3.3 maxAgeI - Max Age for Images

Parameter	maxAge
Description	Set the duration (in seconds) to store images, in the client cache, from the product on the client browser.
Ordinality	Mandatory
Valid Values	As per J2EE Standards . Default: 28850
Source	Derived from WEB_MAXAGEI parameter from ENVIRON.INI. It is highly recommended to set to the default unless otherwise recommended.
Applicability	WEB
Example	<pre><filter> <filter-name>Image Browser Cache Filter</filter-name> <filter- class>com.splwg.base.web.services.BrowserCacheFilter</filter- class> <init-param> <param-name>maxAge</param-name> <param-value>28850</param-value> </init-param> </filter></pre>

A.3.4 maxAge - Max Age for Pages

Parameter	maxAge
Description	Set the duration (in seconds) to store page structures from the product, in the client cache, on the client browser.
Ordinality	Mandatory
Valid Values	As per J2EE Standards. Default: 28850
Source	Derived from WEB_MAXAGE parameter from ENVIRON.INI. It is highly recommended to set to the default unless otherwise recommended.
Applicability	WEB
Example	<pre> <filter> <filter-name>Browser Cache Filter</filter-name> <filter- class>com.splwg.base.web.services.BrowserCacheFilter</filter- class> <init-param> <param-name>maxAge</param-name> <param-value>28850</param-value> </init-param> </filter> </pre>

A.3.5 auth-method - Authorization Method

Parameter	auth-method
Description	Sets the J2EE authentication method for the product.
Ordinality	Mandatory
Valid Values	[BASIC CLIENT-CERT FORM]
Source	<p>Derived from WEB_WLAUTHMETHOD parameter from ENVIRON.INI. Depending on the value this may lead to further settings being implemented.</p> <ul style="list-style-type: none"> • BASIC - Enables the operating system to provide the logon dialog. • CLIENT-CERT - Enables an external solution such as a SSO solution, Kerberos or any security implementing client certificates to provide credentials. • DIGEST - Use digest authentication³⁰. • FORM - This instructs the product to implement the following additional settings: <ul style="list-style-type: none"> ○ WEB_FORM_LOGIN_PAGE and WEB_HELP_FORM_LOGIN_ERROR_PAGE need to be set to indicate the form to use for online authentication. ○ WEB_HELP_FORM_LOGIN_PAGE and WEB_FORM_LOGIN_ERROR_PAGE need to be set to indicate the form to use for online help authentication. ○ WEB_APPVIEWER_FORM_LOGIN_PAGE and WEB_APPVIEWER_FORM_LOGIN_ERROR_PAGE need to be set to indicate the form to use for AppViewer authentication. <p>Note: Appviewer must be enabled for this setting to apply.</p>
Applicability	WEB
Example	<pre> <login-config> <auth-method>FORM</auth-method> <form-login-config> <form-login-page>/loginPage.jsp</form-login-page> <form-error-page>/formLoginError.jsp</form-error-page> </form-login-config> </login-config> </pre>

³⁰ Not supported for an external LDAP provider or custom provider within Oracle WebLogic. Digest Authentication is only supported if SIP is installed with Oracle WebLogic.

A.3.6 fieldValuesAge - Server Cache Lifetime

Parameter	fieldValuesAge
Description	Set the duration (in seconds) to hold data in the server data cache.
Ordinality	Mandatory
Valid Values	1 - 2147483647 Default: 3600
Source	Defaulted from template. Changes to the value require a custom template.
Applicability	WEB BAS
Example	<pre><env-entry> <description>How long to cache drop down values in seconds</description> <env-entry-name>fieldValuesAge</env-entry-name> <env-entry-type>java.lang.Integer</env-entry-type> <env-entry-value>3600</env-entry-value> </env-entry></pre>

A.3.7 disableUIPageCompression - Disable UI Compression

Parameter	disableUIPageCompression
Description	Enables or disables compression between the browser and Web Application Server (true or false).
Ordinality	Mandatory
Valid Values	[true false]
Source	Derived from <code>WEB_ISDEVELOPMENT</code> parameter from <code>ENVIRON.INI</code> . It is highly recommended to set to false for all environment exception is development environments using Oracle Utilities SDK.
Applicability	WEB
Example	<pre><env-entry> <description>Disable UIPage compression</description> <env-entry-name>disableUIPageCompression</env-entry-name> <env-entry-type>java.lang.Boolean</env-entry-type> <env-entry-value>false</env-entry-value> </env-entry></pre>

A.4 spl.properties

The spl.properties file is used by each layer of the product to configure the technical aspects of the product behavior. All settings in this file are of the format:

<parameter>=<parameter value>

A.4.1 calendar.japanese.eras - Japanese Era Definition

Parameter	calendar.japanese.eras
Description	<p>This is a set of strings defining the era used in the Japanese calendar. The string is a collection of the following tags (one set per era separated with a ";" delimiter):</p> <ul style="list-style-type: none"> • name - Name of era • abbr - Era Abbreviation • since - Date era starts in ISO format (YYYY-MM-DD) • endDate - Date era ends in ISO format (YYYY-MM-DD) • japAbbr - The Japanese character for the era in Unicode format <p>Note: This feature is only appropriate if the Japanese language pack is also installed.</p>
Ordinality	Mandatory
Valid Values	String set by implementations
Source	Value inherited from templates. Use custom template to set this value, if desired.
Applicability	BAS BATCH
Example	<pre>calendar.japanese.eras=name:Taisho,abbr:T,since:1912-07-30,endDate:1926-12-24,japAbbr:\u5927\u6B63;name:Showa,abbr:S,since:1926-12-25,endDate:1989-01-07,japAbbr:\u662D\u548C; name:Heisei,abbr:H,since:1989-01-08,endDate:,japAbbr:\u5E73\u6210</pre>

A.4.2 com.oracle.ouaf.allowed.file.locations – XML File with Substitution Variable Definitions

Parameter	com.oracle.ouaf.allowed.file.locations
Description	XML file that contains list of allowed directories and their corresponding substitution variables.
Ordinality	Mandatory if file parameter validation is enabled.
Valid Values	XML file along with the directory path.
Source	Value inherited from CLOUD_SUBSTITUTION_VARIABLE_LIST_FILE_LOCATION in the ENVIRON.INI file.
Applicability	BAS
Example	<pre>com.oracle.ouaf.allowed.filelocations=@SPLEBASE@/etc/ \substitutionVariableList.xml</pre> <p>The installed product base directory is defaulted from SPLEBASE value in ENVIRON.INI</p>

A.4.3 com.oracle.ouaf.customer.whitelist.file – Customer's URL Whitelist File

Parameter	com.oracle.ouaf.customer.whitelist.file
Description	Full directory path to the URL customer's whitelist file to be checked for restricting URLs.
Ordinality	Optional
Valid Values	Location of whitelist URL file, along with filename.
Source	Defaulted from the CLOUD_CUSTOM_WHITE_LIST_PATH value in ENVIRON.INI.
Applicability	BAS
Example	<pre>com.oracle.ouaf.customer.whitelist.file=@SPLEBASE@/etc/ cm_whitelist.xml</pre> <p>The installed product base directory is defaulted from SPLEBASE value in ENVIRON.INI</p>

A.4.4 com.oracle.ouaf.fileParamValidation.enable – File Parameter Validation

Parameter	com.oracle.ouaf.fileParamValidation.enable
Description	Enable or disable file Parameter validation that will enforce usage of the predefined substitution variables as a file parameter value.

Ordinality	Mandatory
Valid Values	[true false].
Source	Defaulted from the CLOUD_FILE_PARAMETER_VALIDATION value in ENVIRON.INI.
Applicability	BAS
Example	com.oracle.ouaf.fileParamValidation.enable=true

A.4.5 com.oracle.ouaf.migrationAssistant.exportDirectory

– Directory for Exported CMA File

Parameter	com.oracle.ouaf.migrationAssistant.exportDirectory
Description	Contains a directory specification, using the defined substitution variable @F1_MIGR_ASSISTANT_FILES@, in the white list.
Ordinality	Optional
Valid Values	Location of the CMA export file on the server.
Source	Value inherited from templates. Use custom template to set this value.
Applicability	BAS BATCH
Example	com.oracle.ouaf.migrationAssistant.exportDirectory=@F1_MIGR_ASSISTANT_FILES@/export

A.4.6 com.oracle.ouaf.migrationAssistant.importDirectory

– Directory for CMA File for Import

Parameter	com.oracle.ouaf.migrationAssistant.importDirectory
Description	Contains a directory specification, using the defined substitution variable @F1_MIGR_ASSISTANT_FILES@, in the white list.
Ordinality	Optional
Valid Values	Location of the CMA import file on the server.
Source	Value inherited from templates. Use custom template to set this value.
Applicability	BAS BATCH
Example	com.oracle.ouaf.migrationAssistant.importDirectory=@F1_MIGR_ASSISTANT_FILES@/import

A.4.7 com.oracle.ouaf.migrationAssistant.fileExtension – Extension of CMA File

Parameter	com.oracle.ouaf.migrationAssistant.fileExtension
Description	Specifies the file extention of the CMA file.
Ordinality	Optional
Valid Values	File Extentions.
Source	Value inherited from templates. Use custom template to set this value.
Applicability	BAS BATCH
Example	com.oracle.ouaf.migrationAssistant.fileExtension=cma

A.4.8 com.oracle.ouaf.system.database.disableTagging - Disables Database Tagging

Parameter	com.oracle.ouaf.system.database.disableTagging
Description	This enables (false) or disables (true) the database connection tagging feature. Note: Disabling this feature can reduce monitoring capabilities, disable support for Oracle Audit Vault, disable session resource management in Oracle Real Application Clusters and disable advanced support for Database resource plans.
Ordinality	Mandatory
Valid Values	[true false]
Source	Value inherited from templates. Use custom template to set this value to true, if desired.
Applicability	WEB BAS IWS XAI BATCH MOB
Example	com.oracle.ouaf.system.database.disableTagging=false

A.4.9 com.oracle.ouaf.system.keystore.alias - Keystore Alias

Parameter	com.oracle.ouaf.system.keystore.alias
Description	Sets name alias in keystore. Corresponds to the alias option on keytool.
Ordinality	Mandatory
Valid Values	Set to ouaf.system.
Source	This value is set by the KS_ALIAS value in ENVIRON.INI.

Applicability	WEB	BAS	IWS	XAI	BATCH	MOB
Example	com.oracle.ouaf.system.keystore.alias=ouaf.system					

A.4.10 com.oracle.ouaf.system.keystore.hmac_key_alias - HMAC Alias

Parameter	com.oracle.ouaf.system.keystore.hmac_key_alias
Description	Sets HMAC name alias in keystore. Corresponds to the alias option on keytool.
Ordinality	Mandatory
Valid Values	Set to ouaf.system.hmac by default.
Source	This value is set by the KS_HMAC_ALIAS value in ENVIRON.INI.
Applicability	WEB
Example	com.oracle.ouaf.system.keystore.hmac_key_alias=ouaf.system.hmac

A.4.11 com.oracle.ouaf.system.keystore.file - Location of Keystore

Parameter	com.oracle.ouaf.system.keystore.file
Description	Location of keystore file. Corresponds to the keystore option on keytool. This entry should not be altered.
Ordinality	Mandatory
Valid Values	Set to full path location of keystore and name of keystore file.
Source	Defaulted to \$SPLBASE/ks/.ouaf_keystore (or for Windows %SPLBASE%\ks\.ouaf_keystore) from the KS_KEYSTORE_FILE value in ENVIRON.INI.
Applicability	WEB
Example	com.oracle.ouaf.system.keystore.file=/opt/.ouaf_keystore

A.4.12 com.oracle.ouaf.system.keystore.mode - Keystore Mode

Parameter	com.oracle.ouaf.system.keystore.mode
Description	Mode of the keystore. This is not used to create the keystore, just how the product processes the keys inside.
Ordinality	Mandatory
Valid Values	Set to valid keystore mode. Defaulted to CBC.
Source	This value is set from the KS_MODE value in ENVIRON.INI.
Applicability	WEB BAS IWS XAI BATCH MOB
Example	com.oracle.ouaf.system.keystore.mode=CBC

A.4.13 com.oracle.ouaf.system.keystore.padding - Key Padding

Parameter	com.oracle.ouaf.system.keystore.padding
Description	Padding used for keys. This is not used to create the keystore, just how the product processes the keys inside.
Ordinality	Mandatory
Valid Values	Set to valid keystore mode. Defaulted to PKCS5Padding.
Source	This value is set from the KS_PADDING value in ENVIRON.INI.
Applicability	WEB BAS IWS XAI BATCH MOB
Example	com.oracle.ouaf.system.keystore.padding=PKCS5Padding

A.4.14 com.oracle.ouaf.system.keystore.passwordFileName - Password File

Parameter	com.oracle.ouaf.system.keystore.passwordFileName
Description	Location of keystore password file. Corresponds to the <code>storepass</code> option on keytool. This entry should not be altered.
Ordinality	Mandatory
Valid Values	Set to full path location of keystore and name of keystore file.
Source	Defaulted to <code>\$SPLBASE/ks/.ouaf_storepass</code> (or for Windows <code>%SPLBASE%\ks\.ouaf_storepass</code>) from the <code>KS_STOREPASS_FILE</code> value in <code>ENVIRON.INI</code> .
Applicability	WEB BAS IWS XAI BATCH MOB
Example	<code>com.oracle.ouaf.system.keystore.passwordFileName=/spl/OUAFDEMO/ks/.ouaf_storepass</code>

A.4.15 com.oracle.ouaf.system.keystore.type - Keystore Type

Parameter	com.oracle.ouaf.system.keystore.type
Description	Keystore Type. Corresponds to the <code>storetype</code> option on keytool.
Ordinality	Mandatory
Valid Values	Set to valid keystore mode. Defaulted to <code>JCEKS</code> .
Source	This value is set from the <code>KS_STORETYPE</code> value in <code>ENVIRON.INI</code> .
Applicability	WEB BAS IWS XAI BATCH MOB
Example	<code>com.oracle.ouaf.system.keystore.type=JCEKS</code>

A.4.16 com.oracle.ouaf.system.truststore.file - Location of Truststore

Parameter	com.oracle.ouaf.system.truststore.file
Description	Location of truststore file. Corresponds to the truststore option on keytool.
Ordinality	Mandatory
Valid Values	Set to full path location of truststore and name of truststore file.
Source	Defaulted from the TS_KEYSTORE_FILE value in ENVIRON.INI.
Applicability	BAS
Example	com.oracle.ouaf.system.truststore.file=/opt/.ouaf_trstore

A.4.17 com.oracle.ouaf.system.truststore.passwordFileName - Location of Truststore Password file

Parameter	com.oracle.ouaf.system.truststore.passwordFileName
Description	Location of truststore password file.
Ordinality	Mandatory
Valid Values	Set to full path location of truststore password file.
Source	Defaulted from the TS_STOREPASS_FILE value in ENVIRON.INI.
Applicability	BAS
Example	com.oracle.ouaf.system.truststore.passwordFileName=/opt/.ouaf_trstorepass

A.4.18 com.oracle.ouaf.truststore.type - Type of Truststore

Parameter	com.oracle.ouaf.truststore.type
Description	Type of truststore file.
Ordinality	Mandatory
Valid Values	Sets Type of Truststore.
Source	Defaulted from the TS_STORETYPE value in ENVIRON.INI.
Applicability	BAS
Example	com.oracle.ouaf.system.truststore.file=/opt/.ouaf_trstore

A.4.19 com.oracle.ouaf.urlValidator.enable – Enable Restriction of URLs

Parameter	com.oracle.ouaf.urlValidator.enable
Description	Enable URL validation. Restricts external URLs based on white list filename.
Ordinality	Mandatory for cloud installations. Optional for on premise installations.
Valid Values	[true false]. Default value is false
Source	Defaulted from the CLOUD_RESTRICTION_URLS_ENABLE value in ENVIRON.INI.
Applicability	BAS
Example	com.oracle.ouaf.urlValidator.enable=false

A.4.20 com.oracle.ouaf.whitelist.file – Oracle URL Whitelist Filename and Location

Parameter	com.oracle.ouaf.whitelist.file
Description	Full directory path to the URL oracle whitelist file to be checked for restricting URLs.
Ordinality	Mandatory if restriction is activated.
Valid Values	Location of whitelist URL file, along with filename.
Source	Defaulted from the CLOUD_WHITE_LIST_PATH value in ENVIRON.INI.
Applicability	BAS
Example	com.oracle.ouaf.whitelist.file=@SPLEBASE@/etc/whitelist.xml The installed product base directory is defaulted from SPLEBASE value in ENVIRON.INI

A.4.21 com.oracle.ouaf.xsd.dir - Location of XSD Files for XAI

Parameter	com.oracle.ouaf.xsd.dir
Description	Full directory path to XSD schemas used for XML Application Integration. This replaces the XAI Options versions of this setting.
Ordinality	Mandatory
Valid Values	Location of schemas. Typically set to splapp/xai/schemas directory under software install location.
Source	Generated
Applicability	XAI

Example	com.oracle.ouaf.xsd.dir=/spl/OUAFDEMO/splapp/xai/schemas
----------------	--

A.4.22 com.oracle.ouaf.xsl.dir - Location of XSL Files for XAI

Parameter	com.oracle.ouaf.xsl.dir
Description	Full directory path to XSLT style sheets used for XML Application Integration. This replaces the XAI Options versions of this setting.
Ordinality	Mandatory
Valid Values	Location of XSL files. Typically set to splapp/xai/schemas directory under software install location.
Source	Generated
Applicability	XAI
Example	com.oracle.ouaf.xsl.dir=/spl/OUAFDEMO/splapp/xai/schemas

A.4.23 com.oracle.XPath.LRUSize - XPath Cache

Parameter	com.oracle.XPath.LRUSize
Description	Sets Maximum XPath queries cached used in Schema based objects.
Ordinality	Optional
Valid Values	0 - No queries cached, -1 - Unlimited (7k per query), Value - Number of queries.
Source	Uses XQUERIES_TO_CACHE value in ENVIRON.INI
Applicability	BAS MOB BATCH
Example	com.oracle.XPath.LRUSize=2000

A.4.24 com.oracle.XPath.flushTimeout - XPath Flush

Parameter	com.oracle.XPath.flushTimeout
Description	Sets time (in seconds) to reset XPath cache.
Ordinality	Optional
Valid Values	0 - Never auto flush, Value - Time in seconds between flushes.
Source	Uses XQUERY_CACHE_FLUSH_TIMEOUT value in ENVIRON.INI
Applicability	BAS BATCH MOB
Example	com.oracle.XPath.flushTimeout=86400

A.4.25 com.splwg.batch.cluster.jvmName - Online Batch JVM Name

Parameter	com.splwg.batch.cluster.jvmName
Description	Sets name for monitoring purposes for online batch JVM for online submission. This value is not used by the runtime, just exposed to the JMX interface for categorization purposes.
Ordinality	Optional
Valid Values	Any string without embedded blanks.
Source	Use the spl.properties.root.exit.include user exit to set this value.
Applicability	WEB
Example	com.splwg.batch.cluster.jvmName=onlineBatch

A.4.26 com.splwg.batch.scheduler.daemon - Online Submission Daemon

Parameter	com.splwg.batch.scheduler.daemon
Description	Enable or Disable the Batch Daemon for online submission. The Batch Daemon is used to detect Pending Batch Submission objects and send them to Batch Online servers. It is highly recommended to specify a value of false for Production environments. The Batch Daemon is only recommended to be used, set to true, in Testing, Development or Demonstration environments.
Ordinality	Mandatory
Valid Values	[true false]
Source	Derived from BATCHDAEMON parameter from ENVIRON.INI.
Applicability	BAS
Example	com.splwg.batch.scheduler.daemon=false

A.4.27 com.splwg.grid.executionMode - Online Execution Mode

Parameter	com.splwg.grid.executionMode
Description	Sets the execution mode of the online Batch submission.
Ordinality	Mandatory

Valid Values	[THIN CLUSTERED]
Source	Derived from BATCH_MODE parameter from ENVIRON.INI.
Applicability	BAS
Example	com.splwg.grid.executionMode=CLUSTERED

A.4.28 com.splwg.grid.online.enabled - Online Batch Server

Parameter	com.splwg.grid.online.enabled
Description	Enable or Disable the Batch Server for online submission. The Batch Server is responsible for managing and executing jobs allocated by the Batch Daemon. It is highly recommended to specify a value of false for Production environments. The Batch Server is only recommended to be used in Testing, Development or Demonstration environments.
Ordinality	Mandatory
Valid Values	[true false]
Source	Derived from BATCHENABLED parameter from ENVIRON.INI.
Applicability	BAS
Example	com.splwg.grid.online.enabled=false

A.4.29 com.splwg.grid.distThreadPool.threads.DEFAULT - Online Submission Threadpool

Parameter	com.splwg.grid.distThreadPool.threads.DEFAULT
Description	Maximum number of concurrent threads used to execute online submission. This setting is used in conjunction with the Online Batch Server setting.
Ordinality	Mandatory
Valid Values	1 - 1000. Default: 5
Source	Derived from BATCHTHREADS parameter from ENVIRON.INI.
Applicability	BAS
Example	com.splwg.grid.distThreadPool.threads.DEFAULT=5

A.4.30 com.splwg.schema.newValidations.F1 - Set Behavior of Validations

Parameter	com.splwg.schema.newValidations.F1
Description	Sets behavior of schema validations. Internal use only. This is set by individual products and should not be altered unless otherwise instructed by Oracle Support.
Ordinality	Mandatory
Valid Values	[true false]
Source	Value inherited from templates. Use custom template to set this value to false, if desired.
Applicability	WEB BAS
Example	com.splwg.schema.newValidations.F1=true

A.4.31 jmx.remote.x.access.file - JMX Access Control

Parameter	jmx.remote.x.access.file
Description	Sets relative location of JMX access control file holding the valid user. Refer to JMX Security for more details.
Ordinality	Mandatory
Valid Values	Relative location of file from \$SPLBASE/%SPLBASE%. Defaults to scripts/ouaf.jmx.access.file
Source	Value inherited from templates. Use custom template to set this value to the desired location and file, if desired.
Applicability	WEB BAS
Example	jmx.remote.x.access.file=scripts/ouaf.jmx.access.file

A.4.32 jmx.remote.x.password.file - JMX Password Control

Parameter	jmx.remote.x.password.file
Description	Sets relative location of JMX password file holding the valid passwords for jmx.remote.x.access.file. Refer to JMX Security for more details.
Ordinality	Mandatory
Valid Values	Relative location of file from \$SPLBASE/%SPLBASE%. Defaults to scripts/ouaf.jmx.password.file
Source	Value inherited from templates. Use custom template to set this value to the desired location and file, if desired.
Applicability	WEB BAS
Example	jmx.remote.x.password.file=scripts/ouaf.jmx.password.file

A.4.33 oracle.ouaf.jmx.remote.startPort - JMX Override Port

Parameter	oracle.ouaf.jmx.remote.startPort
Description	Alternative port number for JMX monitoring. Allows for overrides from standard port. Overrides spl.runtime.management.rmi.port.
Ordinality	Optional
Valid Values	Valid port numbers. Defaults to spl.runtime.management.rmi.port
Source	Specif.
Applicability	WEB BAS
Example	jmx.remote.x.password.file=scripts/ouaf.jmx.password.file

A.4.34 ouaf.accessibility.features - Enable Accessibility Features

Parameter	ouaf.accessibility.features
Description	Enables or disabled accessibility support from the product, specifically around implementing tabIndex for column headers. Other accessibility features are not altered by this setting.
Ordinality	Mandatory
Valid Values	[true false]
Source	Value inherited from templates. Use custom template to set this value to false, if desired.
Applicability	WEB
Example	ouaf.accessibility.features=true

A.4.35 ouaf.attachment.disableSpecialCharCheckOnFileName - Disable Special Characters on File Name

Parameter	ouaf.attachment.disableSpecialCharCheckOnFileName
Description	Disables (true) or enables (false) check for special characters used in file name for attachment objects.
Ordinality	Mandatory
Valid Values	[true false]
Source	Value inherited from templates. Use custom template to set this value to true, if desired.
Applicability	BAS
Example	ouaf.attachment.disableSpecialCharCheckOnFileName=false

A.4.36 ouaf.batch.onlineLogDir - Online Line Batch Log Directory

Parameter	ouaf.batch.onlineLogDir
Description	Sets the location of output from online batch submission and batch scheduler integration. If this property is set, batch logs will be accessible via the Batch Run Tree (application UI). Otherwise, the batch logs download link in the application will be disabled.
Ordinality	Optional
Valid Values	Valid location. Defaults to: \$SPLOUTPUT (%SPLOUTPUT% on Windows)
Source	Value inherited from BATCH_ONLINE_LOG_DIR from ENVIRON.INI.
Applicability	BATCH
Example	ouaf.batch.onlineLogDir=/tmp

A.4.37 ouaf.batch.onlineLogDir.retain – Retain Online Line Batch Log Files

Parameter	ouaf.batch.onlineLogDir.retain
Description	Sets the total number of log files that are to be stored for each batch code and thread number. The log files for the particular batch code and thread number will be deleted except for the latest number of logs specified.
Ordinality	Optional
Valid Values	Number
Source	Generated by template. Use bedit to implement a different value.
Applicability	BATCH
Example	ouaf.batch.onlineLogDir.retain=3 The above example will keep the last three logs and delete the rest.

A.4.38 ouaf.database.session.setInstallationTimeZone - Set Time Zone for Sessions

Parameter	ouaf.database.session.setInstallationTimeZone
Description	Set this property to true if the Time Zone on the installation record via the online Installation Options - Framework menu item (under Main tab) is different to the default timezone on the database. This will ensure session timezone is corrected.

Ordinality	Mandatory
Valid Values	[true false]
Source	Value inherited from templates. Use custom template to set this value to true, if desired.
Applicability	BAS MOB BATCH
Example	ouaf.database.session.setInstallationTimeZone=false

A.4.39 ouaf.flush.jms.disabled - Global Flush supported

Parameter	ouaf.flush.jms.disabled
Description	Enables (false) or disables (true) global flush feature.
Ordinality	Optional
Valid Values	[true false]
Source	Value inherited from templates. Use custom template to set this value to false, if desired.
Applicability	WEB BAS IWS BATCH MOB
Example	ouaf.flush.jms.disabled=true

A.4.40 ouaf.flush.jms.connection - Connection Factory for Global Flush

Parameter	ouaf.flush.jms.connection
Description	JNDI Name for Global JMS connection
Ordinality	Optional
Valid Values	Valid JNDI for JMS Connection Factory. Default: jms/OUFlushConnectionFactory
Source	Value inherited from templates. Use custom template to set this value to an alternative value, if desired.
Applicability	WEB BAS IWS BATCH MOB
Example	ouaf.flush.jms.connection=jms/OUFlushConnectionFactory

A.4.41 ouaf.flush.jms.requestTopic - Global Flush Request Topic

Parameter	ouaf.flush.jms.requestTopic
Description	JNDI Name for Global JMS Request Topic
Ordinality	Optional
Valid Values	Valid JNDI for JMS Request Topic. Default: jms/OUFlushRequestTopic
Source	Value inherited from templates. Use custom template to set this value to an alternative value, if desired.
Applicability	WEB BAS IWS BATCH MOB
Example	ouaf.flush.jms.requestTopic=jms/OUFlushRequestTopic

A.4.42 ouaf.flush.jms.responseTopic - Global Flush Response Topic

Parameter	ouaf.flush.jms.responseTopic
Description	JNDI Name for Global JMS Response Topic
Ordinality	Optional
Valid Values	Valid JNDI for JMS Response Topic. Default: jms/OUFlushResponseTopic
Source	Value inherited from templates. Use custom template to set this value to an alternative value, if desired.
Applicability	WEB BAS IWS BATCH MOB
Example	ouaf.flush.jms.responseTopic=jms/OUFlushResponseTopic

A.4.43 ouaf.runtime.compatibility.enablePrecisionScaleOnMoney - Money Processing

Parameter	ouaf.runtime.compatibility.enablePrecisionScaleOnMoney
Description	Enables or disabled precision checking on money fields.
Ordinality	Mandatory
Valid Values	[true false]
Source	Value inherited from templates. Use custom template to set this value to false, if desired.

Applicability	WEB
Example	ouaf.runtime.compatibility.enablePrecisionScaleOnMoney=false

A.4.44 ouaf.jmx.com.oracle.ouaf.ws.mbeans.WSFlushBean - WS Cache Flush

Parameter	ouaf.jmx.com.oracle.ouaf.ws.mbeans.WSFlushBean
Description	Enables or disables the Flush Mbean used for the online JMX monitoring. Refer to the Web Services JMX interface for more information. This parameter is only enabled if the JMX interface is enabled.
Ordinality	Mandatory
Valid Values	[enabled disabled]
Source	Value inherited from templates. Use custom template to set this value to disabled, if desired.
Applicability	IWS
Example	ouaf.jmx.com.oracle.ouaf.ws.mbeans.WSFlushBean=enabled

A.4.45 ouaf.jmx.com.splwg.base.support.management.mbean.JVMInfo - JVM Information

Parameter	ouaf.jmx.com.splwg.base.support.management.mbean.JVMInfo
Description	Enables or disables the JVMInfo Mbean used for the online JMX monitoring. Refer to the Web Application Server JMX interface for more information. This parameter is only enabled if the JMX interface is enabled.
Ordinality	Mandatory
Valid Values	[enabled disabled]
Source	Value inherited from templates. Use custom template to set this value to disabled, if desired.
Applicability	WEB
Example	ouaf.jmx.com.splwg.base.support.management.mbean.JVMInfo=enabled

A.4.46 ouaf.jmx.com.splwg.base.web.mbeans.FlushBean - Manage Cache

Parameter	ouaf.jmx.com.splwg.base.web.mbeans.FlushBean
Description	Enables or disables the Mbean to reset the online data cache manually. Refer to the Web Application Server JMX interface for more information. This parameter is only enabled if the JMX interface is enabled.
Ordinality	Mandatory
Valid Values	[enabled disabled]
Source	Value inherited from templates. Use custom template to set this value to disabled, if desired.
Applicability	WEB
Example	ouaf.jmx.com.splwg.base.web.mbeans.FlushBean=enabled

A.4.47 ouaf.list.buffer.limit - List Iteration limit

Parameter	ouaf.list.buffer.limit
Description	The number of iterations a list is allowed to be read before being truncated. A default of 30 is used, if none or an invalid value is specified for this property.
Ordinality	Optional
Valid Values	Value between 0 - 256
Source	Value inherited from J2EE container. Use custom template to set this value, if alternative desired
Applicability	BAS
Example	ouaf.list.buffer.limit=30

A.4.48 ouaf.messaging.transformerfactory - Transformer

Parameter	ouaf.messaging.transformerfactory
Description	Sets the transformation factory for the real time adapters. This parameter is only set if requested by Oracle Support.
Ordinality	Optional
Valid Values	Set to one of the following values: com.sun.org.apache.xalan.internal.xsltc.trax.TransformerFactoryImpl org.apache.xalan.xsltc.trax.TransformerFactoryImpl
Source	Value inherited from J2EE container. Use custom template to set this value, if alternative desired
Applicability	BAS BATCH
Example	ouaf.messaging.transformerfactory = org.apache.xalan.xsltc.trax.TransformerFactoryImpl

A.4.49 ouaf.shortcut.ignore.altKeys - Disable Hot Keys

Parameter	ouaf.shortcut.ignore.altKeys
Description	Allows specific hot keys to be disabled to support specific keyboard layouts (e.g. Polish keyboards).
Ordinality	Optional
Valid Values	Comma separated list of keys to disable
Source	Set within template. Use the spl.properties.root.exit.include user exit to set this value.

Applicability	WEB
Example	ouaf.shortcut.ignore.altKeys=C,L

A.4.50 ouaf.timeout.business_object.default - Set Default Business Object Timeout

Parameter	ouaf.timeout.business_object.default
Description	Sets the default timeout (in seconds) for Business Objects. Refer to Online Transaction Timeouts for more information.
Ordinality	Optional
Valid Values	1 - 2147483647
Source	Use the spl.properties.service.timeouts.exit.include user exit to set this value as outlined in Online Transaction Timeouts.
Applicability	BAS
Example	ouaf.timeout.business_object.default=10

A.4.51 ouaf.timeout.business_object.<bocode> - Set Specific Business Object Timeout

Parameter	ouaf.timeout.business_object.<bocode>
Description	Sets the timeout (in seconds) for Business Object designated by <bocode> which corresponds to the Business Object Name. This overrides the ouaf.timeout.business_object.default setting for the indicated business object. Refer to Online Transaction Timeouts for more information. To find valid values for Business Objects, use the Business Object Maintenance function or use the following SQL: <pre>SELECT bus_obj_cd, descr FROM f1_bus_obj_1 where language_cd = 'ENG';</pre> The LANGUAGE_CD in the above query can be altered to other languages for language packs installed.
Ordinality	Optional
Valid Values	1 - 2147483647
Source	Use the spl.properties.service.timeouts.exit.include user exit to set this value as outlined in Online Transaction Timeouts.
Applicability	BAS

Example	ouaf.timeout.business_object.CMUser=10
----------------	--

A.4.52 ouaf.timeout.business_service.default - Set Default Business Service Timeout

Parameter	ouaf.timeout.business_service.default
Description	Sets the default timeout (in seconds) for Business Services. Refer to Online Transaction Timeouts for more information.
Ordinality	Optional
Valid Values	1 - 2147483647
Source	Use the spl.properties.service.timeouts.exit.include user exit to set this value as outlined in Online Transaction Timeouts.
Applicability	BAS
Example	ouaf.timeout.business_service.default=10

A.4.53 ouaf.timeout.business_service.<bscode> - Set Specific Business Service Timeout

Parameter	ouaf.timeout.business_service.<bscode>
Description	Sets the timeout (in seconds) for Business Service designated by <bscode> which corresponds to the Business Service Name. This overrides the ouaf.timeout.business_service.default setting for the indicated business service. Refer to Online Transaction Timeouts for more information. To find valid values for Business Services, use the Business Service Maintenance function or use the following SQL: SELECT bus_svc_cd, descr FROM f1_bus_svc_1 where language_cd = 'ENG'; The LANGUAGE_CD in the above query can be altered to other languages for language packs installed
Ordinality	Optional
Valid Values	1 - 2147483647
Source	Use the spl.properties.service.timeouts.exit.include user exit to set this value as outlined in Online Transaction Timeouts.
Applicability	BAS
Example	ouaf.timeout.business_service.F1-EmailService=10

A.4.54 ouaf.timeout.query.default - Set Default Query Timeout

Parameter	ouaf.timeout.query.default
Description	<p>Sets the default timeout (in seconds) for query zones (searches and lists). Refer to Online Transaction Timeouts for more information.</p> <p>Use the Zone maintenance function to determine valid values.</p> <p>This setting only applies to the following zone types:</p> <p>F1-DE, F1-DE-MULQRY, F1-DE-QUERY and F1-DE-SINGLE</p>
Ordinality	Optional
Valid Values	1 - 2147483647
Source	Use the spl.properties.service.timeouts.exit.include user exit to set this value as outlined in Online Transaction Timeouts.
Applicability	BAS
Example	ouaf.timeout.query.default=10

A.4.55 ouaf.timeout.query.<zonecode> - Set Specific Query Timeout

Parameter	ouaf.timeout.query.<zonecode>
Description	<p>Sets the timeout (in seconds) for the online query zone designated by <zonecode> which corresponds to the Query Zone. This overrides the ouaf.timeout.query.default setting for the indicated query zone. Refer to Online Transaction Timeouts for more information. This setting only applies to the following zone types:</p> <p>F1-DE, F1-DE-MULQRY, F1-DE-QUERY and F1-DE-SINGLE</p> <p>Use the Zone maintenance function to determine valid values.</p> <p>Alternatively it is possible to use SQL to find the ZONE_CD's <zonecode>:</p> <pre>SELECT z.zone_cd, d.descr, z.zone_hdl_cd FROM ci_zone z, ci_zone_l d WHERE z.zone_hdl_cd LIKE 'F1-DE%' AND z.zone_cd = d.zone_cd AND d.language_cd = 'ENG';</pre> <p>The LANGUAGE_CD in the above query can be altered to other languages for language packs installed.</p>
Ordinality	Optional
Valid Values	1 - 2147483647
Source	Use the spl.properties.service.timeouts.exit.include user exit to set this value as

	outlined in Online Transaction Timeouts.
Applicability	BAS
Example	ouaf.timeout.business_service.F1-MSTCFGELS=10

A.4.56 ouaf.timeout.script.default - Set Default Script Timeout

Parameter	ouaf.timeout.script.default
Description	Sets the default timeout (in seconds) for Scripts. Refer to Online Transaction Timeouts for more information.
Ordinality	Optional
Valid Values	1 - 32767
Source	Use the spl.properties.service.timeouts.exit.include user exit to set this value as outlined in Online Transaction Timeouts.
Applicability	BAS
Example	ouaf.timeout.script.default=10

A.4.57 ouaf.timeout.script.<scriptname> - Set Specific Script Timeout

Parameter	ouaf.timeout.script.<scriptname>
Description	Sets the timeout (in seconds) for Scripts designated by <scriptname> which corresponds to the Script Name. This overrides the ouaf.timeout.script.default setting for the indicated script. Refer to Online Transaction Timeouts for more information.
	Note: This timeout does not apply to plug-in scripts.
	To find valid values for Script, use the Script Maintenance function or use the following SQL: SELECT s.scr_cd, d.descr254 FROM ci_scr s, ci_scr_l d where s.scr_cd = d.scr_cd and s.scr_type_flg in ('BPSC', 'SVSC') and d.language_cd = 'ENG'; The LANGUAGE_CD in the above query can be altered to other languages for language packs installed
Ordinality	Optional
Valid Values	1 - 2147483647

Source	Use the spl.properties.service.timeouts.exit.include user exit to set this value as outlined in Online Transaction Timeouts.
Applicability	BAS
Example	ouaf.timeout.script.F1-ViewWSDL=10

A.4.58 ouaf.timeout.service.default - Set Default Service Timeout

Parameter	ouaf.timeout.service.default
Description	Sets the default timeout (in seconds) for Application Services. Refer to Online Transaction Timeouts for more information.
Ordinality	Optional
Valid Values	1 - 2147483647
Source	Use the spl.properties.service.timeouts.exit.include user exit to set this value as outlined in Online Transaction Timeouts.
Applicability	BAS
Example	ouaf.timeout.service.default=10

A.4.59 ouaf.timeout.service.<service> - Set Specific Service Timeout

Parameter	ouaf.timeout.service.<service>
Description	Sets the timeout (in seconds) for Application Services designated by <service> which corresponds to the Application Service Name. This overrides the ouaf.timeout.service.default setting for the indicated Application Service. Refer to Online Transaction Timeouts for more information. To find valid values for Application Service, use the Application Service Maintenance function or use the following SQL: SELECT SVC_NAME, DESCRIPTOR from CI_MD_SVC_L where language_cd = 'ENG'; The LANGUAGE_CD in the above query can be altered to other languages for language packs installed
Ordinality	Optional
Valid Values	1 - 2147483647
Source	Use the spl.properties.service.timeouts.exit.include user exit to set this value as outlined in Online Transaction Timeouts.

Applicability	BAS
Example	ouaf.timeout.service.CILTUSEP=10

A.4.60 ouaf.web.appViewer.coreAppURL - AppViewer Callback URL

Parameter	ouaf.web.appViewer.coreAppURL
Description	URL for AppViewer to navigate back to the product.
Ordinality	Mandatory
Valid Values	Generated URL from WEB_WLHOST, WEB_WLPORT, WEB_WLSSLPORT and WEB_CONTEXT_ROOT.
Source	Value inherited from templates. Use custom template to set this value to desired value.
Applicability	WEB
Example	ouaf.web.appViewer.coreAppURL= http://localhost:6500/ouaf/loginPage.jsp#fromAppViewer

A.4.61 ouaf.web.disablePreload - Disable Screen Preload

Parameter	ouaf.web.disablePreload
Description	Enables or disables screen preloading at startup. Screens that are preloaded are autoloaded at startup rather than at first use, saving time at runtime for first use transactions. This parameter works in conjunction with ouaf.web.preloadAllPages. It is highly recommended to set this value to false (default) for Production Environments. It is only suggested to set this to true in development environments that are used in conjunction with the Oracle Utilities SDK.
Ordinality	Mandatory
Valid Values	[true false]
Source	Derived from WEB_ISDEVELOPMENT parameter from ENVIRON.INI. It is highly recommended to set to the default unless otherwise recommended
Applicability	WEB
Example	ouaf.web.help.coreAppURL= http://localhost:6500/ouaf/loginPage.jsp

A.4.62 ouaf.web.help.coreAppURL - Help Callback URL

Parameter	ouaf.web.help.coreAppURL
Description	URL for Help to navigate back to the product.
Ordinality	Mandatory
Valid Values	Generated URL from WEB_WLHOST, WEB_WLPORT, WEB_WLSSLPORT and WEB_CONTEXT_ROOT.
Source	Value inherited from templates. Use custom templates to set this value to desired value.
Applicability	WEB
Example	ouaf.web.help.coreAppURL=.../.../ouaf/loginPage.jsp

A.4.63 ouaf.web.helpRootURL - Help URL

Parameter	ouaf.web.helpRootURL
Description	URL for Help for help requests from online.
Ordinality	Mandatory
Valid Values	Generated URL from WEB_WLHOST, WEB_WLPORT, WEB_WLSSLPORT and WEB_CONTEXT_ROOT.
Source	Value inherited from templates. Use custom templates to set this value to desired value.
Applicability	WEB
Example	ouaf.web.helpRootURL=/ouaf/help/

A.4.64 ouaf.web.JspHeader.maxAge - JSP Age

Parameter	ouaf.web.JspHeader.maxAge
Description	Set the duration (in seconds) to screen HTML, in the client cache, from the product on the client browser.
Ordinality	Mandatory
Valid Values	As per J2EE Standards. Default: 28850
Source	Derived from WEB_MAXAGE parameter from ENVIRON.INI. It is highly recommended to set to the default unless otherwise recommended.
Applicability	WEB
Example	ouaf.web.JspHeader.maxAge=28850

A.4.65 ouaf.web.preloadAllPages - Preload Scope

Parameter	ouaf.web.preloadAllPages
Description	Set the scope of the preloading of pages. This parameter is only used if the ouaf.web.disablePreload is set to false. It is highly recommended to set this value to false (default) for all environments.
Ordinality	Mandatory
Valid Values	[true false] - Main menu only (false), Main menu and Administration menu (true)
Source	Derived from WEB_PRELOADALL parameter from ENVIRON.INI. It is highly recommended to set to the default unless otherwise recommended.
Applicability	WEB
Example	ouaf.web.preloadAllPages=false

A.4.66 ouaf.web.useOHW - Use Oracle Help for Web Engine

Parameter	ouaf.web.useOHW
Description	Use the Oracle Help for Web engine rather than the legacy SPLHelp engine. This setting is only applicable to Oracle WebLogic customers. Customers on IBM WebSphere must use the SPLHelp engine.
Ordinality	Mandatory
Valid Values	[true false]
Source	Value inherited from templates. Use custom template to set this value to false, if desired.
Applicability	WEB
Example	ouaf.web.useOHW=true

A.4.67 ouaf.weblogic.enableDiagnostics - Enable ECID Tracking

Parameter	ouaf.weblogic.enableDiagnostics
Description	Enables (true) or disable (false) ECID feature.
Ordinality	Mandatory
Valid Values	[true false]
Source	Value inherited from templates. Use custom template to set this value to true, if desired.
Applicability	WEB
Example	ouaf.weblogic.enableDiagnostics = false

A.4.68 ouaf.webservices.security.defaultPolicy – IWS Customized Security Policy

Parameter	ouaf.webservices.security.defaultPolicy
Description	Sets the customized policy for the deployed IWS.
Ordinality	Mandatory
Valid Values	[true false]
Source	Value inherited from templates. Use custom template to set this value to true, if desired.

Applicability	WEB
Example	ouaf.weblogic.enableDiagnostics = false

A.4.69 ouaf.ws.defaultUser - Default User for Web Services

Parameter	ouaf.ws.defaultUser
Description	Default user used for authorization for Inbound Web Services if no credentials are provided on the Web Service call. This is provided for backward compatibility for XML Application Integration customers. It is recommended not to be set at all, as to enforce stronger security for Web Services.
Ordinality	Optional
Valid Values	Valid authorization user for product. A null or blank value enforces security on each Web Service call.
Source	Defaulted from templates. Use custom templates to set this value to an alternative desired value.
Applicability	IWS
Example	ouaf.ws.defaultUser=AUSER

A.4.70 ouaf.ws.deploy.appxml.file - Application XML File for Inbound Web Services

Parameter	ouaf.ws.deploy.appxml.file
Description	Location of application.xml file for Web Services.
Ordinality	Mandatory
Valid Values	Valid Path and location.
Source	Derived from template. This should not be changed.
Applicability	IWS
Example	ouaf.ws.deploy.appxml.file=/spl/ouaf/iws/resources/application.xml

A.4.71 ouaf.ws.deploy.ear - EAR File Name for Inbound Web Services

Parameter	ouaf.ws.deploy.ear
Description	Name of EAR file used for Inbound Web Services
Ordinality	Optional

Valid Values	Valid authorization user for product. A null or blank value enforces security on each Web Service call.
Source	Derived from template Use custom templates to set this value to an alternative desired value.
Applicability	IWS
Example	ouaf.ws.deploy.ear=Weservices.ear

A.4.72 ouaf.ws.deploy.contextpath - Context Path for Inbound Web Services

Parameter	ouaf.ws.deploy.contextpath
Description	Default context path used for Inbound Web Services calls
Ordinality	Optional
Valid Values	Valid authorization user for product. A null or blank value enforces security on each Web Service call.
Source	Derived from template Use custom templates to set this value to an alternative desired value.
Applicability	IWS
Example	ouaf.ws.deploy.contextpath=/ouaf/webservices/

A.4.73 ouaf.ws.deploy.user - Web Services Deployment User

Parameter	ouaf.ws.deploy.user
Description	J2EE Administration account used to deploy Inbound Web Services container. Password for this user is contained in keystore as outlined in Enabling Inbound Web Services.
Ordinality	Mandatory
Valid Values	Valid Administration account for J2EE container.
Source	Derived from WLS_WEB_WLSYSUSER parameter from ENVIRON.INI. Use custom templates to set this value to an alternative desired value.
Applicability	IWS
Example	ouaf.ws.deploy.user=system

A.4.74 ouaf.ws.pageService.annotations - Security Annotation for XAI Legacy services

Parameter	ouaf.ws.pageService.annotations
Description	The default security WS-Policy annotations attached for legacy page services (XAI) within IWS. To ensure backward compatibility, for customers using XAI legacy services, it is recommended to set this value to the default F1-USERNAM annotation.
Ordinality	Optional
Valid Values	Valid Web Service Annotation
Source	Defaulted from templates. Use custom templates to set this value to an alternative desired value.
Applicability	IWS
Example	ouaf.ws.pageService.annotations=F1-USERNAM

A.4.75 ouaf.ws.superusers - Effective Web Services Users

Parameter	ouaf.ws.superusers
Description	Sets the effective users for Inbound Web Services. This allows credentials from foreign systems to use credentials from the product. This is only set to alternatives if effective users are used.
Ordinality	Mandatory
Valid Values	Valid comma separated list of credentials
Source	Derived from WEB_SPLUSER parameter from ENVIRON.INI. Use custom templates to set this value to an alternative desired value.
Applicability	IWS
Example	ouaf.ws.superusers=SYSUSER

A.4.76 ouaf.ws.tools.artifact.generated.buildfile - Build File

Parameter	ouaf.ws.tools.artifact.generated.buildfile
Description	Location and name of ant build file used to generate the WAR file used for Inbound Web Services. This setting is used by the iwsdeploy.sh command as well as the online Inbound Web Services deployment tool.
Ordinality	Mandatory
Valid Values	Location and name of build file. Defaults to \$SPLBASE/splapp/iws/iws-build.xml (or %\$SPLBASE%\splapp\iws\iws-build.xml on Windows)
Source	Derived from SPLDIR parameter from ENVIRON.INI. Use custom template to set this value to an alternative desired value.
Applicability	IWS
Example	ouaf.ws.tools.artifact.generated.buildfile=/spl/OUAFDEMO/splapp/iws/iws-build.xml

A.4.77 ouaf.ws.tools.artifact.generated.sourcedir - Location of Generated Source

Parameter	ouaf.ws.tools.artifact.generated.sourcedir
Description	Location of the source generated for Inbound Web Services during the Web Services deployment process.
Ordinality	Mandatory
Valid Values	Location of generated source directory. Defaults to \$SPLBASE/splapp/iws/gen (or %\$SPLBASE%\splapp\iws\gen on Windows)
Source	Derived from SPLDIR parameter from ENVIRON.INI. Use custom templates to set this value to an alternative desired value.
Applicability	IWS
Example	ouaf.ws.tools.artifact.generated.sourcedir=/spl/OUAFDEMO/splapp/iws/gen

A.4.78 ouaf.ws.tools.artifact.resource.dir - Location of 319 Resources

Parameter	ouaf.ws.tools.artifact.resource.dir
Description	Location of the resource files used in the generation of Inbound Web Services during the Web Services deployment process.
Ordinality	Mandatory
Valid Values	Location of resources used for Inbound Web Services. Defaults to \$SPLEBASE/splapp/iws/resources (or %\$SPLEBASE%\splapp\iws\resources on Windows)
Source	Derived from SPLDIR parameter from ENVIRON.INI. Use custom templates to set this value to an alternative desired value.
Applicability	IWS
Example	ouaf.ws.tools.artifact.resource.dir= /spl/OUAFDEMO/splapp/iws/resources

A.4.79 ouaf.ws.tools.artifact.schema.dir - Location of Schemas

Parameter	ouaf.ws.tools.artifact.schema.dir
Description	Location of the schema files used in the generation of Inbound Web Services during the Web Services deployment process.
Ordinality	Mandatory
Valid Values	Location of schema files used for Inbound Web Services. Defaults to \$SPLEBASE/splapp/xai/schemas (or %\$SPLEBASE%\splapp\xai\schemas on Windows)
Source	Derived from SPLDIR parameter from ENVIRON.INI. Use custom templates to set this value to an alternative desired value.
Applicability	IWS
Example	ouaf.ws.tools.artifact.schema.dir= /spl/OUAFDEMO/splapp/xai/schemas

A.4.80 ouaf.ws.tools.artifact.xsl.dir - Web Service XSL Location

Parameter	ouaf.ws.tools.artifact.xsl.dir
Description	Location of the XSLT files used by Inbound Web Services during the Web Services deployment process. This parameter can be overridden using the ouaf.ws.xslDirOverride setting.
Ordinality	Mandatory
Valid Values	Location of XSLT files used for Inbound Web Services. Defaults to \$SPLBASE/splapp/xai/schemas (or %\$SPLBASE%\splapp\xai\schemas on Windows). By default this value is shared with ouaf.ws.tools.artifact.schema.dir.
Source	Derived from SPLDIR parameter from ENVIRON.INI. Use custom templates to set this value to an alternative desired value.
Applicability	IWS
Example	ouaf.ws.tools.artifact.xsl.dir= /spl/OUAFDEMO/splapp/xai/schemas

A.4.81 ouaf.ws.tracing - Inbound Web Services Tracing

Parameter	ouaf.ws.tracing
Description	Enable or Disable tracing for Inbound Web Services.
Ordinality	Mandatory
Valid Values	[true false]
Source	Defaulted from templates. Use custom templates to set this value to an alternative desired value.
Applicability	IWS
Example	ouaf.ws.tracing=true

A.4.82 ouaf.ws.xslDirOverride - Override XSL Location

Parameter	ouaf.ws.xslDirOverride
Description	Location of the XSLT files used by Inbound Web Services during the Web Services deployment process. This parameter overrides the ouaf.ws.tools.artifact.xsl.dir setting.
Ordinality	Mandatory
Valid Values	Valid directories on server containing xsl For Windows environments, use the file protocol.
Source	Not set. Use custom templates to set this value to an alternative desired value.
Applicability	IWS
Examples	ouaf.ws.xslDirOverride=/temp ouaf.ws.xslDirOverride=file:///c:/temp

A.4.83 ouaf.xai.HTTPBasicAuthPasswordEnc - Default XAI Password

Parameter	ouaf.xai.HTTPBasicAuthPasswordEnc
Description	Encrypted password for default application user for XML Application Integration.
Ordinality	Mandatory
Valid Values	Encrypted password for users.
Source	Derived from WEB_SPLPASS parameter from ENVIRON.INI.
Applicability	WEB
Example	ouaf.xai.HTTPBasicAuthPasswordEnc=ENC(unj0oM7+zufXI5r6Q...)

A.4.84 ouaf.xai.HTTPBasicAuthUser - Default XAI User

Parameter	ouaf.xai.HTTPBasicAuthUser
Description	Default application user for XML Application Integration.
Ordinality	Mandatory
Valid Values	Valid Application User
Source	Derived from WEB_SPLPUSER parameter from ENVIRON.INI.
Applicability	WEB
Example	ouaf.xai.HTTPBasicAuthUser=SYSUSER

A.4.85 ouaf.xai.XAI Server URL - Default XAI URL

Parameter	ouaf.xai.XAI Server URL
Description	Default URL for XML Application Integration.
Ordinality	Mandatory
Valid Values	Generated URL for XAI Server from WEB_WLHOST, WEB_WLPORT and WEB_CONTEXT_ROOT from ENVIRON.INI.
Source	Use custom templates to set this value to an alternative, if desired.
Applicability	WEB
Example	ouaf.xai.XAI Server URL= http://localhost:6500/ouaf/XAIApp/xaiserver

A.4.86 spl.csv.delimiter.useFromDisplayProfile - List CSV Delimiter

Parameter	spl.csv.delimiter.useFromDisplayProfile
Description	Enables or disables the display of the delimiter for CSV upload/downloads from zones.
Ordinality	Mandatory
Valid Values	[true false]
Source	Derived from template. Use custom templates to set this value to true, if desired.
Applicability	WEB
Example	spl.csv.delimiter.useFromDisplayProfile=false

A.4.87 `spl.ejbContainer.contextFactory` - Context Factory for Business Application Server

Parameter	<code>spl.ejbContainer.contextFactory</code>
Description	Default J2EE Context Factory to connect tiers.
Ordinality	Mandatory
Valid Values	Valid connection factory: Oracle WebLogic: <code>weblogic.jndi.WLInitialContextFactory</code> IBM WebSphere/IBM WebSphere ND: <code>com.ibm.websphere.naming.WsnInitialContextFactory</code>
Source	Derived from template. Use custom templates to set this value to an alternative, if desired.
Applicability	WEB IWS
Example	<code>spl.ejbContainer.contextFactory=weblogic.jndi.WLInitialContextFactory</code>

A.4.88 `spl.ejbContainer.password` - Password for Business Application Server

Parameter	<code>spl.ejbContainer.password</code>
Description	Default encrypted password for tier defined for Business Application Server connections.
Ordinality	Mandatory
Valid Values	Valid password encrypted Administration user
Source	Oracle WebLogic: <code>WEB_WLSYSPASS</code> from <code>ENVIRON.INI</code> IBM WebSphere/IBM WebSphere ND: <code>WEB_WASPASS</code> from <code>ENVIRON.INI</code> Use custom templates to set this value to an alternative, if desired.
Applicability	WEB IWS
Example	<code>spl.ejbContainer.password=ENC(Hi7/RFy...)</code>

A.4.89 `spl.ejbContainer.url` - Business Application Server URL

Parameter	<code>spl.ejbContainer.url</code>
Description	URL to connect to the Business Application Server from the Web Application Server or Inbound Web Services.
Ordinality	Mandatory
Valid Values	Valid URL for: Oracle WebLogic: <code>t3://<server>:<port></code> or <code>t3s://<server>:<port></code> IBM WebSphere/IBM WebSphere ND: <code>iiop://<server>:<port></code>
Source	Derived from template. Use custom templates to set this value to an alternative, if desired.
Applicability	WEB IWS
Example	<code>spl.ejbContainer.url = t3://localhost:6500</code>

A.4.90 `spl.ejbContainer.user` - Business Application Server User

Parameter	<code>spl.ejbContainer.user</code>
Description	Administration user for Business Application server who can connect from the Web Application Server and Inbound Web Services.
Ordinality	Mandatory
Valid Values	Valid Administration User on J2EE Server
Source	Oracle WebLogic: <code>WEB_WLSYSUSER</code> from <code>ENVIRON.INI</code> IBM WebSphere/IBM WebSphere ND: <code>WEB_WASUSER</code> from <code>ENVIRON.INI</code> Use custom templates to set this value to an alternative, if desired.
Applicability	WEB IWS
Example	<code>spl.ejbContainer.user=system</code>

A.4.91 `spl.geocodeDatasource.contextFactory` - GIS Context Factory

Parameter	<code>spl.geocodeDatasource.contextFactory</code>
Description	Default J2EE Context Factory to connect to GIS. This option will only be enabled if GIS is set to true in the ENVIRON.INI.
Ordinality	Mandatory
Valid Values	<p>Valid connection factory:</p> <p>Oracle WebLogic: <code>weblogic.jndi.WLInitialContextFactory</code></p> <p>IBM WebSphere/IBM WebSphere ND: <code>com.ibm.websphere.naming.WsnInitialContextFactory</code></p>
Source	Derived from template. Use custom templates to set this value to an alternative, if desired.
Applicability	WEB BAS BATCH
Example	<code>spl.geocodeDatasource.contextFactory=weblogic.jndi.WLInitialContextFactory</code>

A.4.92 `spl.geocodeDatasource.password` - GIS Connection Password

Parameter	<code>spl.geocodeDatasource.password</code>
Description	Encrypted password for GIS connection for <code>spl.geocodeDatasource.user</code> . This option will only be enabled if GIS is set to true in the ENVIRON.INI.
Ordinality	Mandatory
Valid Values	Encrypted password for GIS.
Source	Derived from <code>GIS_WLSYSPASS</code> from ENVIRON.INI
Applicability	WEB BAS BATCH
Example	<code>spl.geocodeDatasource.password=ENC(Hi7/RFy...)</code>

A.4.93 `spl.geocodeDatasource.url` - GIS Data Source

Parameter	<code>spl.geocodeDatasource.url</code>
Description	JNDI name for GIS Data Source. This option will only be enabled if GIS is set to true in the ENVIRON.INI.
Ordinality	Mandatory
Valid Values	Valid JNDI path for GIS Data Source
Source	Derived from GIS_WLSYSUSER from ENVIRON.INI
Applicability	WEB BAS BATCH
Example	<code>spl.geocodeDatasource.url=t3://localhost:7666/jdbc/gisdb</code>

A.4.94 `spl.geocodeDatasource.user` - GIS Connection User

Parameter	<code>spl.geocodeDatasource.user</code>
Description	Valid JNDI user for GIS connection. This option will only be enabled if GIS is set to true in the ENVIRON.INI.
Ordinality	Mandatory
Valid Values	Encrypted password for GIS.
Source	Derived from GIS_WLSYSUSER from ENVIRON.INI
Applicability	WEB BAS BATCH
Example	<code>spl.geocodeDatasource.user=gisadmin</code>

A.4.95 `spl.mwm.abr.contextFactory` - ABR Context Factory

Parameter	<code>spl.mwm.abr.contextFactory</code>
Description	Default J2EE Context Factory to connect to Appointment Booking Reservation (ABR) component.
Ordinality	Mandatory
Valid Values	Valid connection factory: Oracle WebLogic: <code>weblogic.jndi.WLInitialContextFactory</code> IBM WebSphere/IBM WebSphere ND: <code>com.ibm.websphere.naming.WsnInitialContextFactory</code>
Source	Derived from CONTEXTFACTORY from ENVIRON.INI
Applicability	MOB
Example	<code>spl.mwm.abr.contextFactory=weblogic.jndi.WLInitialContextFactory</code>

A.4.96 `spl.mwm.abr.password` - ABR Connection Password

Parameter	<code>spl.mwm.abr.password</code>
Description	Encrypted password for Appointment Booking Reservation (ABR) component connection for <code>spl.mwm.abr.user</code> .
Ordinality	Mandatory
Valid Values	Encrypted password for ABR.
Source	Derived from WLS_PASSWORD from ENVIRON.INI
Applicability	MOB
Example	<code>spl.mwm.abr.password=ENC(Hi7/RFy...)</code>

A.4.97 **spl.mwm.abr.timeout** - Timeout for ABR

Parameter	spl.mwm.abr.timeout
Description	Connection timeout, in seconds, for Appointment Booking Reservation (ABR) component.
Ordinality	Mandatory
Valid Values	1 - 2147483647 (Default: 120000)
Source	Derived from TIMEOUT from ENVIRON.INI
Applicability	MOB
Example	spl.mwm.abr.timeout=120000

A.4.98 **spl.mwm.abr.url** - ABR URL

Parameter	spl.mwm.abr.url
Description	URL to connect to the Appointment Booking Reservation (ABR) component.
Ordinality	Mandatory
Valid Values	Valid URL for: Oracle WebLogic: t3://<server>:<port> or t3s://<server>:<port> IBM WebSphere/IBM WebSphere ND: iiop://<server>:<port>
Source	Derived from URL from ENVIRON.INI
Applicability	MOB
Example	spl.abr.url = t3://localhost:7751

A.4.99 `spl.mwm.abr.userid` - ABR Connection User

Parameter	<code>spl.mwm.abr.user</code>
Description	Valid JNDI user for Appointment Booking Reservation (ABR) component connection.
Ordinality	Mandatory
Valid Values	Encrypted connection user for GIS.
Source	Derived from WLS_USERID from ENVIRON.INI
Applicability	MOB
Example	<code>spl.mwm.abr.userid=ENC(ho4tqPhP...)</code>

A.4.100 `spl.mwm.scheduler.abr.maxProcessingTime` - Processing Time for ABR

Parameter	<code>spl.mwm.scheduler.abr.maxProcessingTime</code>
Description	Transaction timeout, in seconds, for each appointment booking processed by Appointment Booking Reservation (ABR) component.
Ordinality	Mandatory
Valid Values	1 - 2147483647 (Default: 5)
Source	Derived from MAXPROCESSINGTIME from ENVIRON.INI
Applicability	MOB
Example	<code>spl.mwm.scheduler.abr.maxProcessingTime=5</code>

A.4.101 `spl.mwm.scheduler.abr.minRequests` - Initial Scheduler Pool Size

Parameter	<code>spl.mwm.scheduler.abr.minRequests</code>
Description	Initial request pool size for Appointment Booking Reservation (ABR) component.
Ordinality	Mandatory
Valid Values	1 - 2147483647 (Default: 1)
Source	Derived from MINREQUESTS from ENVIRON.INI
Applicability	MOB
Example	<code>spl.mwm.scheduler.abr.minRequests=1</code>

A.4.102 `spl.mwm.scheduler.cleanse.interval` - Scheduler Cache Clense

Parameter	<code>spl.mwm.scheduler.cleanse.interval</code>
Description	Prefresh time, in seconds, for scheduler cache with product.
Ordinality	Mandatory
Valid Values	1 - 2147483647 (Default: 900)
Source	Derived from CLEANSE_INTERVAL from ENVIRON.INI
Applicability	MOB
Example	<code>spl.mwm.scheduler.cleanse.interval=900</code>

A.4.103 `spl.mwm.scheduler.connectionTimeout` - Scheduler Connection Timeout

Parameter	<code>spl.mwm.scheduler.connectionTimeout</code>
Description	Connection timeout, in seconds, between product and scheduler.
Ordinality	Mandatory
Valid Values	1 - 2147483647 (Default: 300000)
Source	Derived from SCHED_CONN_TIMEOUT from ENVIRON.INI
Applicability	MOB
Example	<code>spl.mwm.scheduler.connectionTimeout=300000</code>

A.4.104 `spl.mwm.scheduler.maintenanceCycleTime` - Scheduler Integrity Check

Parameter	<code>spl.mwm.scheduler.maintenanceCycleTime</code>
Description	Time, in seconds, between scheduler integrity checks.
Ordinality	Mandatory
Valid Values	1 - 2147483647 (Default: 300)
Source	Derived from SCHED_CYCLE_TIMEOUT from ENVIRON.INI
Applicability	MOB
Example	<code>spl.mwm.scheduler.maintenanceCycleTime=300</code>

A.4.105 `spl.mwm.scheduler.mapDir` - Map Directory

Parameter	<code>spl.mwm.scheduler.mapDir</code>
Description	Location of Map files if external maps are used.
Ordinality	Mandatory
Valid Values	Valid Directory
Source	Derived from MAPDIR from ENVIRON.INI
Applicability	MOB
Example	<code>spl.mwm.scheduler.mapDir=/spl/splapp/OUAFDEMO/sploutput</code>

A.4.106 `spl.mwm.scheduler.nodeId` - Scheduler Node

Parameter	<code>spl.mwm.scheduler.nodeId</code>
Description	Node Identifier for Scheduler. This setting is used for backward compatibility only as Scheduler now dynamically determines nodes.
Ordinality	Mandatory
Valid Values	Valid Node Id (If used must match Scheduler object)
Source	Derived from NODEID from ENVIRON.INI
Applicability	MOB
Example	<code>spl.mwm.scheduler.nodeId=MyNode</code>

A.4.107 `spl.runtime.mwm.scheduler.ipcStartPort` - IPC Start Port

Parameter	<code>spl.runtime.mwm.scheduler.ipcStartPort</code>
Description	Starting port number for Inter Process Communication (IPC) between the scheduler and products.
Ordinality	Mandatory
Valid Values	Valid port numbers. Schedulers allocate port numbers starting from this number.
Source	Derived from IPCSTARTPORT from ENVIRON.INI
Applicability	MOB
Example	<code>spl.runtime.mwm.scheduler.ipcStartPort=7568</code>

A.4.108 `spl.runtime.compatibility.uiMapDisableInputValue` - Map Defaults

Parameter	<code>spl.runtime.compatibility.uiMapDisableInputValue</code>
Description	<p>Enables or disables compatibility behavior with Oracle Utilities Application Framework V2.1 in relation to blanking out default values in screens.</p> <p>Setting this value to true will emulate Oracle Utilities Application Framework V2.1 behavior.</p> <p>This setting is only applicable to customers who are upgrading from Oracle Utilities Application Framework V2.1 and wish to retain that behavior.</p>
Ordinality	Optional
Valid Values	[true false]
Source	Manually set. Use user exit <code>spl.properties.exit.include</code> to set this value to true, if desired
Applicability	WEB
Example	<code>spl.runtime.compatibility.uiMapDisableInputValue=false</code>

A.4.109 `spl.runtime.compatibility.uiMapDropdownSelectFirstValue` - Dropdown Defaults

Parameter	<code>spl.runtime.compatibility.uiMapDropdownSelectFirstValue</code>
Description	<p>Enables or disables compatibility behavior with Oracle Utilities Application Framework V2.1 in relation to defaulting to the first value in dropdownlist.</p> <p>Setting this value to true will emulate Oracle Utilities Application Framework V2.1 behavior.</p> <p>This setting is only applicable to customers who are upgrading from Oracle Utilities Application Framework V2.1 and wish to retain that behavior.</p>
Ordinality	Optional
Valid Values	[true false]
Source	Manually set. Use user exit <code>spl.properties.exit.include</code> to set this value to true, if desired
Applicability	WEB
Example	<code>spl.runtime.compatibility.uiMapDropdownSelectFirstValue=false</code>

A.4.110 `spl.runtime.compatibility.uiMapDisableTitle` - Screen Title Defaults

Parameter	<code>spl.runtime.compatibility.uiMapDisableTitle</code>
Description	<p>Enables or disables compatibility behavior with Oracle Utilities Application Framework V2.1 in relation to rendering screen titles.</p> <p>Setting this value to true will emulate Oracle Utilities Application Framework V2.1 behavior.</p> <p>This setting is only applicable to customers who are upgrading from Oracle Utilities Application Framework V2.1 and wish to retain that behavior.</p>
Ordinality	Optional
Valid Values	[true false]
Source	Manually set. Use user exit <code>spl.properties.exit.include</code> to set this value to true, if desired
Applicability	WEB
Example	<code>spl.runtime.compatibility.uiMapDisableTitle=false</code>

A.4.111 `spl.runtime.compatibility.uiMapDisableGenerateUniqueHTMLIDs` - Map IDs

Parameter	<code>spl.runtime.compatibility.uiMapDisableGenerateUniqueHTMLIDs</code>
Description	<p>Enables or disables compatibility behavior with Oracle Utilities Application Framework V2.x in relation to generating a unique identifier's for HTML for duplicate elements in the screen. In Oracle Utilities Application Framework V2.x (true), duplicate HTML ids were permitted on screen elements. In Oracle Utilities Application Framework V4.x (false), unique ids are generated for screen elements by default.</p> <p>Setting this value to true will emulate Oracle Utilities Application Framework V2.x behavior.</p> <p>This setting is only applicable to customers who are upgrading from Oracle Utilities Application Framework V2.x and wish to retain that behavior.</p>
Ordinality	Optional
Valid Values	[true false]
Source	Manually set. Use user exit <code>spl.properties.exit.include</code> to set this value to true, if desired
Applicability	WEB
Example	<code>spl.runtime.compatibility.uiMapDisableGenerateUniqueHTMLIDs=false</code>

A.4.112 `spl.runtime.disableCSRFProtection` - Disable Security Tokens

Parameter	<code>spl.runtime.disableCSRFProtection</code>
Description	<p>Enables or disables security token support for testing purposes with testing tools that do not support security tokens.</p> <p>It is highly recommended that this configuration setting be set to false in all environments, especially Production.</p> <p>It should only be set to true in testing environments where test tools are used and the test tool used does not support security tokens.</p>
Ordinality	Optional
Valid Values	[true false]
Source	Manually set. Use user exit <code>spl.properties.exit.include</code> to set this value to true, if desired
Applicability	WEB
Example	<code>spl.runtime.disableCSRFProtection=false</code>

A.4.113 `spl.runtime.environ.init.dir` - Location of Configuration Files

Parameter	<code>spl.runtime.environ.init.dir</code>
Description	Location of the configuration files used for the product. This is used to allow the product to read configuration files at runtime to determine behavior.
Ordinality	Mandatory
Valid Values	URL is derived from <code>spl.runtime.environ.SPLEBASE</code> with the <code>etc</code> directory appended.
Source	Derived from <code>cistab</code> file.
Applicability	WEB BAS IWS
Example	<code>spl.runtime.environ.init.dir=/spl/OUAFDEMO/etc</code>

A.4.114 `spl.runtime.environ.isWebExpanded` - Expanded Mode

Parameter	<code>spl.runtime.environ.isWebExpanded</code>
Description	<p>Determines whether WAR/EAR files are built [false] or as expanded directories [true]. The expanded mode is used for development purposes only and is only supported on Oracle WebLogic.</p> <p>It is recommended to set this to false to use WAR/EAR files for deployment.</p>
Ordinality	Mandatory
Valid Values	[true false]
Source	Derived from WEB_ISEXPANDED parameter from ENVIRON.INI.
Applicability	WEB BAS
Example	<code>spl.runtime.environ.isWebExpanded=false</code>

A.4.115 `spl.runtime.environ.SPLEBASE` - Location of Software

Parameter	<code>spl.runtime.environ.SPLEBASE</code>
Description	Home directory of the product installation
Ordinality	Mandatory
Valid Values	Full expanded directory on machine
Source	Derived from <code>cistab</code> file.
Applicability	WEB BAS IWS XAI BATCH
Example	<code>spl.runtime.environ.SPLEBASE=/spl/OUAFDEMO</code>

A.4.116 `spl.runtime.initialize.waittime` - Start Time Delay

Parameter	<code>spl.runtime.initialize.waittime</code>
Description	Delay Time (in seconds) for start of application from initiation time. This is used to delay startup to ensure downstream connections are established prior to startup.
Ordinality	Optional
Valid Values	0 - 3000 (Default: 45)
Source	Derived from templates. Use custom templates to set this value to an alternative, if desired
Applicability	IWS
Example	<code>spl.runtime.initialize.waittime = 45</code>

A.4.117 `spl.runtime.environ.SPLOUTPUT` - Location of Output

Parameter	<code>spl.runtime.environ.SPLOUTPUT</code>
Description	Home directory of the product output
Ordinality	Mandatory
Valid Values	Full expanded directory on machine
Source	Derived from cistab file.
Applicability	WEB BAS IWS XAI BATCH
Example	<code>spl.runtime.environ.SPLOUTPUT=/spl/splapp/OUAFDEMO</code>

A.4.118 `spl.runtime.management.batch.cluster.url` - Batch Cluster URL

Parameter	<code>spl.runtime.management.batch.cluster.url</code>
Description	URL for the Batch Cluster
Ordinality	Mandatory
Valid Values	Valid URL for Batch Cluster
Source	Derived from WEB_BATCH_CLUSTER_URL parameter from ENVIRON.INI.
Applicability	WEB
Example	<code>spl.runtime.management.batch.cluster.url=</code>

A.4.119 `spl.runtime.management.connector.url.default` - JMX URL

Parameter	<code>spl.runtime.management.connector.url.default</code>
Description	JMX formatted URL to be used for JMX based monitoring.
Ordinality	Optional
Valid Values	<p>URL is generated from the following settings:</p> <p>Web Application Server:</p> <code>WEB_WLHOST and WEB_JMX_RMI_PORT_PERFORMANCE</code> <p>Business Application Server:</p> <code>BSN_WLHOST and BSN_JMX_RMI_PORT_PERFORMANCE</code> <p>Inbound Web Services:</p> <code>BSN_WLHOST and BSN_JMX_RMI_PORT_PERFORMANCE</code>
Source	Derived from <code>ENVIRON.INI</code> file.
Applicability	WEB BAS IWS
Example	<code>spl.runtime.environ.SPLEBASE=</code> <code>service:jmx:rmi:///jndi/rmi://localhost:</code> <code>1100/oracle/ouaf/ejbAppConnector</code>

A.4.120 `spl.runtime.management.rmi.port` - JMX Port

Parameter	<code>spl.runtime.management.rmi.port</code>
Description	Port number to be used for JMX based monitoring.
Ordinality	Optional
Valid Values	<p>Port number is generated from the following settings:</p> <p>Web Application Server</p> <code>WEB_JMX_RMI_PORT_PERFORMANCE</code> <p>Business Application Server</p> <code>BSN_JMX_RMI_PORT_PERFORMANCE</code> <p>Inbound Web Services</p> <code>BSN_JMX_RMI_PORT_PERFORMANCE</code> <p>Batch</p> <code>BATCH_RMI_PORT</code>
Source	Derived from <code>ENVIRON.INI</code> file.
Applicability	WEB BAS IWS
Example	<code>spl.runtime.management.rmi.port=1100</code>

A.4.121 `spl.runtime.options.isFCFEnabled` - RAC FCF Enabled

Parameter	<code>spl.runtime.options.isFCFEnabled</code>
Description	Enable or Disable RAC Fast Connection Failover support for database connections. Oracle Notification Services configuration is set by the <code>spl.runtime.options.onsserver=nodes</code> parameter.
Ordinality	Mandatory
Valid Values	[true false]
Source	Derived from ONSCONFIG parameter from ENVIRON.INI.
Applicability	BAS BATCH
Example	<code>spl.runtime.options.isFCFEnabled=false</code>

A.4.122 `spl.runtime.options.onsserver=nodes` - ONS Configuration

Parameter	<code>spl.runtime.options.onsserver=nodes</code>
Description	Specify the Oracle Notification Services (ONS) configuration for Fast Connection Failover support for database connections. Refer to the Oracle Notification Services documentation for details of ONS setup and values for this setting.
Ordinality	Mandatory
Valid Values	Valid ONS configuration string (without the nodes= prefix)
Source	Derived from ONSCONFIG parameter from ENVIRON.INI.
Applicability	BAS BATCH
Example	<code>spl.runtime.options.onsserver=nodes=racnode1:4200, racnode2:4200\nwalletfile= /oracle11/onswalletfile</code>

A.4.123 `spl.runtime.options.allowSystemDateOverride` - Set Testing Date

Parameter	<code>spl.runtime.options.allowSystemDateOverride</code>
Description	Allows the user of system test date override feature for testing. Refer to the Setting the Date for testing purposes for more information. It is highly recommended that this setting should be set to false in Production environments.
Ordinality	Mandatory
Valid Values	[true false]
Source	Manually set. Use custom templates to set this value to true, if desired.
Applicability	WEB BAS
Example	<code>spl.runtime.options.allowSystemDateOverride=false</code>

A.4.124 `spl.runtime.options.createSimpleWebAppContextEnable` - Web Cache Loading

Parameter	<code>spl.runtime.options.createSimpleWebAppContextEnable</code>
Description	Enables or disables cache loading from Web Application Server. Setting this value to true will load the server cache through the Business Application Server. If the cache loading, is desired to be loaded within each tier then set this value to false. It is highly recommended that this setting should be set to true in Production environments.
Ordinality	Optional
Valid Values	[true false]
Source	Manually set. Use user exit <code>spl.properties.exit.include</code> to set this value to false, if desired.
Applicability	WEB
Example	<code>spl.runtime.options.createSimpleWebAppContextEnable=false</code>

A.4.125 `spl.runtime.options.isDevelopmentMode` - Development Mode

Parameter	<code>spl.runtime.options.isDevelopmentMode</code>
Description	<p>Enables or disables Development Mode for the product. Development mode disables and enables key features within the architecture to allow the Oracle Utilities SDK to be used optimally. The following settings are affected by this parameter:</p> <ul style="list-style-type: none"> • Caching is disabled at all layers of the architecture. This can be reenabled manually. • Screen Preloading is disabled. This can be reenabled manually. • Compression is disabled at all layers of the architecture. This can be reenabled manually. • The product is set to expanded mode to allow developers access to individual J2EE objects rather than using WAR/EAR files. <p>It is highly recommended that this setting should be set to false in Production environments.</p> <p>This setting is only set to true where the Oracle Utilities SDK is used directly.</p>
Ordinality	Mandatory
Valid Values	[true false]
Source	Derived from <code>WEB_ISDEVELOPMENT</code> parameter from <code>ENVIRON.INI</code> .
Applicability	WEB BAS IWS XAI
Example	<code>spl.runtime.options.isDevelopmentMode=false</code>

A.4.126 `spl.runtime.oracle.statementCacheSize` - Java SQL Cache Size

Parameter	<code>spl.runtime.oracle.statementCacheSize</code>
Description	Number of SQL statement cached for Java based code. It is highly recommended not to alter this value unless otherwise advised by Oracle Support.
Ordinality	Mandatory
Valid Values	1 - 2147483647 (Default: 300)
Source	Derived from templates. Use custom templates to set this value to an alternative, if desired
Applicability	WEB BAS BATCH
Example	<code>spl.runtime.oracle.statementCacheSize=300</code>

A.4.127 `spl.runtime.performSignedNumberValidation.<product>` - Number Validation

Parameter	<code>spl.runtime.performSignedNumberValidation.<product></code>
Description	Unsigned Number Validation routine used by product. By default a F1 based routine is provided and this setting allows products to provide their own processing. This setting is provided for products only. Implementations should not set this value.
Ordinality	Optional
Valid Values	[true false]
Source	Derived from templates. Use user exit <code>spl.properties.service.exit.include</code> and <code>spl.properties.standalone.exit.include</code> to set this value to an alternative, if desired.
Applicability	BAS BATCH
Example	<code>spl.runtime.performSignedNumberValidation.F1=true</code>

A.4.128 `spl.runtime.service.extraInstallationServices` - Installation Service

Parameter	<code>spl.runtime.service.extraInstallationServices</code>
Description	Specifies the internal service used for checking the installation records at startup time. This setting is used by the products, it is not recommended to be altered, unless otherwise directed by Oracle Support.
Ordinality	Optional
Valid Values	Service Name
Source	By default the service CILTINCP is used internally
Applicability	WEB
Example	<code>spl.runtime.service.extraInstallationServices=CILTINCP</code>

A.4.129 `spl.runtime.sql.highValue` - SQL High Value

Parameter	<code>spl.runtime.sql.highValue</code>
Description	The high value used for parameters by SQL queries. It is highly recommended not to alter this value unless otherwise advised by Oracle Support.
Ordinality	Mandatory
Valid Values	Valid high value generated by installer.
Source	Derived from the HIGHVALUE setting in the ENVIRON.INI
Applicability	WEB BAS BATCH
Example	<code>spl.runtime.sql.highValue=\uF8FF</code>

A.4.130 `spl.runtime.utf8Database` - UTF8 Support

Parameter	<code>spl.runtime.utf8Database</code>
Description	Enables or disables UTF8 support within the product.
Ordinality	Mandatory
Valid Values	[true false]
Source	Derived from the ENCODING (CHAR_BASED_DB) setting in the ENVIRON.INI
Applicability	WEB BAS IWS XAI BATCH
Example	<code>spl.runtime.utf8Database=true</code>

A.4.131 `spl.serviceBean.jndi.name` - JNDI Name for Business Application Server

Parameter	<code>spl.serviceBean.jndi.name</code>
Description	JNDI name for Business Application Server generated by installer. It is highly recommended not to alter this value unless otherwise advised by Oracle Support.
Ordinality	Mandatory
Valid Values	Generated by installer.
Source	Derived from the WEB_CONTEXT_ROOT setting in the ENVIRON.INI
Applicability	WEB IWS XAI
Example	<code>spl.serviceBean.jndi.name=ouaf/servicebean</code>

A.4.132 `spl.tools.loaded.applications` - Loaded Product

Parameter	<code>spl.tools.loaded.applications</code>
Description	<p>List the internal product codes installed under the Oracle Utilities Application Framework.</p> <p>This setting is maintained by the individual products and should not be altered unless otherwise instructed by Oracle Support.</p>
Ordinality	Mandatory
Valid Values	Comma separated list of products
Source	Maintained by product templates
Applicability	WEB BAS IWS XAI BATCH
Example	<code>spl.tools.loaded.applications=base,cm</code>

A.5 `hibernate.properties`

The `hibernate.properties` file defines the connection to the database and the Object to Relational database mapping.

A.5.1 `hibernate.cache.use_second_level_cache` - Use Cache

Parameter	<code>hibernate.cache.use_second_level_cache</code>
Description	Enable or Disable the second level cache, which is enabled by default for classes which specifies a cache mapping. This is disabled by default as Oracle Utilities Application Framework includes its own cache.
Ordinality	Mandatory
Valid Values	[true false]
Source	Maintained by product templates. Use custom templates to implement a different value.
Applicability	BAS IWS XAI BATCH
Example	<code>hibernate.cache.use_second_level_cache = false</code>

A.5.2 hibernate.connection.datasource - JNDI Data Source

Parameter	hibernate.connection.datasource
Description	Enables Data Source support and indicates JNDI data source. This is an alternative to UCP. See JNDI Data Sources for more information. JNDI data sources cannot be used for batch processing.
Ordinality	Mandatory
Valid Values	JNDI path to data source
Source	Maintained by product templates. Use custom templates to implement a different value.
Applicability	BAS IWS XAI
Example	hibernate.connection.datasource=jdbc/ouafdb

A.5.3 hibernate.connection.driver_class - Connection Driver Class

Parameter	hibernate.connection.driver_class
Description	Driver class used by Hibernate.
Ordinality	Mandatory
Valid Values	Valid Driver Class. Default: oracle.jdbc.driver.OracleDriver
Source	Maintained by product templates. Use custom templates to implement a different value.
Applicability	BAS IWS XAI BATCH
Example	hibernate.connection.driver_class = oracle.jdbc.driver.OracleDriver

A.5.4 hibernate.connection.password - Database User Password

Parameter	hibernate.connection.password
Description	Encrypted password for Database User.
Ordinality	Mandatory
Valid Values	Generated Database Password. Value depends on channel: <ul style="list-style-type: none"> • Online uses DBPASS • XAI/IWS uses XAI_DBPASS • Batch uses BATCH_DBPASS
Source	Maintained by product templates. Set appropriate value for user required in required parameter.
Applicability	BAS IWS XAI BATCH
Example	hibernate.connection.password = ENCKS (....)

A.5.5 hibernate.connection.provider_class - Connection Provider

Parameter	hibernate.connection.provider_class
Description	Connection Provider Class for Hibernate. Use the default UCP provider as supplied unless using JDBC Data Sources where com.hibernate.connection.DatasourceConnectionProvider is used instead.
Ordinality	Mandatory
Valid Values	Generated Provider Class. Default: com.splwg.shared.common.UCPConnectionProvider
Source	Maintained by product templates. Use custom templates to implement a different value.
Applicability	BAS IWS XAI BATCH
Example	hibernate.connection.provider_class= com.splwg.shared.common.UCPConnectionProvider

A.5.6 hibernate.connection.release_mode - Connection Release

Parameter	hibernate.connection.release_mode
Description	This parameter controls when a connection is released to the pool. By default the value is set to after_transaction. Whilst other values can be used, for consistency of the connection it is recommended to use the default.
Ordinality	Mandatory
Valid Values	Generated Release Mode. Default: after_transaction
Source	Maintained by product templates. Use custom templates to implement a different value.
Applicability	BAS IWS XAI BATCH
Example	hibernate.connection.release_mode=after_transaction

A.5.7 hibernate.connection.url - JDBC URL

Parameter	hibernate.connection.url
Description	JDBC URL for connection to database.
Ordinality	Mandatory
Valid Values	Generated URL or using override database connection.
Source	Maintained by product templates. Use DB_OVERRIDE_CONNECTION for specific values.
Applicability	BAS IWS XAI BATCH
Example	hibernate.connection.url = jdbc:oracle:thin:@ouafdemo.us.oracle.com:1522:/MYPDB

A.5.8 hibernate.connection.username - Database User

Parameter	hibernate.connection.username
Description	JDBC User for connection.
Ordinality	Mandatory
Valid Values	<p>The value depends on the channel accessed:</p> <ul style="list-style-type: none"> • Online uses DBUSER • XAI/IWS uses XAI_DBUSER • Batch uses BATCH_DBUSER
Source	Maintained by product templates. Set appropriate value for user required in required parameter.
Applicability	BAS IWS XAI BATCH
Example	hibernate.connection.username = CISUSER

A.5.9 hibernate.dialect - Dialect Used

Parameter	hibernate.dialect
Description	This is the SQL dialect (database type) for the database being used. Any valid Hibernate dialect may be used. Refer to http://www.hibernate.org/hib_docs/v3/api/org/hibernate/dialect/package-summary.html for a full list.
Ordinality	Mandatory
Valid Values	Generated Dialect. Default: org.hibernate.dialect.Oracle10gDialect.
Source	Maintained by product templates. Use custom templates to implement a different value.
Applicability	BAS IWS XAI BATCH
Example	hibernate.dialect = org.hibernate.dialect.Oracle10gDialect

A.5.10 hibernate.jdbc.batch_size - JDBC2 Update Support

Parameter	hibernate.jdbc.batch_size
Description	A non-zero value enables use of JDBC2 batch updates by Hibernate.
Ordinality	Mandatory
Valid Values	Generated Value. Default: 30
Source	Maintained by product templates. Use custom templates to implement a different value.
Applicability	BAS IWS XAI BATCH
Example	hibernate.jdbc.batch_size = 30

A.5.11 hibernate.jdbc.fetch_size - Solution Set Size

Parameter	hibernate.jdbc.fetch_size
Description	Determines a hint to the JDBC driver on the number of rows to return in any SQL statement. This is overridden at runtime on zone parameters and commit interval.
Ordinality	Mandatory
Valid Values	Generated Value. Default: 100
Source	Maintained by product templates. Use custom templates to implement a different value.
Applicability	BAS IWS XAI BATCH
Example	hibernate.jdbc.fetch_size = 100

A.5.12 hibernate.max_fetch_depth - Join Fetch Depth

Parameter	hibernate.max_fetch_depth
Description	Sets a maximum depth for the outer join fetch tree for single-ended associations (one-to-one, many-to-one). If you set the value to Zero (0), the default outer join fetching is disabled.
Ordinality	Mandatory
Valid Values	Generated Value. Default: 2
Source	Maintained by product templates. Use custom templates to implement a different value.
Applicability	BAS IWS XAI BATCH
Example	hibernate.max_fetch_depth = 2

A.5.13 hibernate.query.factory_class - HQL Parser

Parameter	hibernate.query.factory_class
Description	The classname of a Query Factory to use for HQL parsing.
Ordinality	Mandatory
Valid Values	Generated Value. Default: org.hibernate.hql.internal.classic.ClassicQueryTranslatorFactory
Source	Maintained by product templates. Use custom templates to implement a different value.
Applicability	BAS IWS XAI BATCH
Example	hibernate.query.factory_class=org.hibernate.hql.internal.classic.ClassicQueryTranslatorFactory

A.5.14 hibernate.query.substitutions - Literal Mappings

Parameter	hibernate.query.substitutions
Description	Mapping from tokens in Hibernate queries to SQL tokens (tokens might be function or literal names, for example).
Ordinality	Mandatory
Valid Values	Generated Value. Default: true 'Y', false 'N'
Source	Maintained by product templates. Use custom templates to implement a different value.
Applicability	BAS IWS XAI BATCH
Example	hibernate.query.substitutions = true 'Y', false 'N'

A.5.15 hibernate.show_sql - Debug Mode

Parameter	hibernate.show_sql
Description	Use of Debug Mode for all SQL Statements. It is highly recommended not to enable debug at this level.
Ordinality	Mandatory
Valid Values	[true false]
Source	Maintained by product templates. Use custom templates to implement a different value.
Applicability	BAS IWS XAI BATCH
Example	hibernate.show_sql = false

A.5.16 hibernate.transaction.factory_class - Transaction Class

Parameter	hibernate.transaction.factory_class
Description	The classname of a Transaction Factory to use with Hibernate Transaction API.
Ordinality	Mandatory
Valid Values	Generated Value. Default: org.hibernate.transaction.JDBCTransactionFactory.
Source	Maintained by product templates. Use custom templates to implement a different value.
Applicability	BAS IWS XAI BATCH
Example	hibernate.transaction.factory_class = org.hibernate.transaction.JDBCTransactionFactory

A.5.17 hibernate.ucp.connection_wait_timeout - UCP Connection Timeout

Parameter	hibernate.ucp.connection_wait_timeout
Description	Specifies how long, in seconds, an application request waits to obtain a connection if there are no longer any connections in the pool
Ordinality	Mandatory
Valid Values	Generated Value. Default: 5
Source	Maintained by product templates. Use custom templates to implement a different value.
Applicability	BAS IWS XAI BATCH
Example	hibernate.ucp.connection_wait_timeout=5

A.5.18 hibernate.ucp.inactive_connection_timeout - Connection Inactivity Timeout

Parameter	hibernate.ucp.inactive_connection_timeout
Description	Specifies how long, in seconds, an available connection can remain idle before it is closed and removed from the pool.
Ordinality	Mandatory
Valid Values	Generated Value. Default: 300
Source	Maintained by product templates. Use custom templates to implement a different value.
Applicability	BAS IWS XAI BATCH
Example	hibernate.ucp.inactive_connection_timeout=300

A.5.19 hibernate.ucp.jmx_enabled - Enable UCP JMX

Parameter	hibernate.ucp.jmx_enabled
Description	Enable or Disable JMX Mbeans for UCP. The Mbeans will appear as additional classes on the existing JMX capabilities for that tier.
Ordinality	Mandatory
Valid Values	[true false]
Source	Maintained by product templates. Use custom templates to implement a different value.
Applicability	BAS IWS XAI BATCH
Example	hibernate.ucp.jmx_enabled=false

A.5.20 hibernate.ucp.max_size - Maximum Pool Size

Parameter	hibernate.ucp.max_size
Description	Maximum Pool size for this tier. Maximum number of active connections to the database.
Ordinality	Mandatory
Valid Values	Generated. Default: 30
Source	Maintained by product templates. Use custom templates to implement a different value.
Applicability	BAS IWS XAI BATCH
Example	hibernate.ucp.max_size=30

A.5.21 hibernate.ucp.max_statements - SQL Buffer Size

Parameter	hibernate.ucp.max_statements
Description	Number of statements cached for performance on this tier.
Ordinality	Mandatory
Valid Values	Generated. Default: 50
Source	Maintained by product templates. Use custom templates to implement a different value.
Applicability	BAS IWS XAI BATCH
Example	hibernate.ucp.max_statements=50

A.5.22 hibernate.ucp.min_size - Minimum Pool Size

Parameter	hibernate.ucp.min_size
Description	Initial Connection Pool size for this tier.
Ordinality	Mandatory
Valid Values	Generated. Default: 1
Source	Maintained by product templates. Use custom templates to implement a different value.
Applicability	BAS IWS XAI BATCH
Example	hibernate.ucp.min_size=1

A.6 submitbatch.properties

The submitbatch.properties controls the behavior of individual batch job threads within the batch architecture. This configuration file exists in two forms:

- A global submitbatch.properties that defines global defaults for the implementation.
- A set of submitbatch.properties files for individual jobs that defines any configuration overrides or specific configuration settings for an individual job.

This section outlines each setting for the configuration file.

Note: It is recommended to use the bedit configuration utility to maintain this configuration file.

A.6.1 com.oracle.ouaf.system.keystore.alias - KeyStore Alias

Parameter	com.oracle.ouaf.system.keystore.alias
Description	Alias used within keystore.
Ordinality	Mandatory
Valid Values	Generated using the KS_ALIAS parameter.
Source	Maintained by product templates. Use custom templates to implement a different value.
Applicability	BATCH
Example	com.oracle.ouaf.system.keystore.alias=thealias

A.6.2 com.oracle.ouaf.system.keystore.file - KeyStore File

Parameter	com.oracle.ouaf.system.keystore.file
Description	Location and name of keystore file for encryption keys.
Ordinality	Mandatory
Valid Values	Generated using the KS_KEYSTORE_FILE parameter.
Source	Maintained by product templates. Use custom templates to implement a different value.
Applicability	BATCH
Example	com.oracle.ouaf.system.keystore.file =/scratch/OUAF/ks/.ouaf_keystore

A.6.3 com.oracle.ouaf.system.keystore.hmac_key_alias - KeyStore Mode

Parameter	com.oracle.ouaf.system.keystore.hmac_key_alias
Description	HMAC Alias used within keystore
Ordinality	Mandatory
Valid Values	Generated using the KS_HMAC_ALIAS parameter.
Source	Maintained by product templates. Use custom templates to implement a different value.
Applicability	BATCH
Example	com.oracle.ouaf.system.keystore.hmac_key_alias=thealiasHMAC

A.6.4 com.oracle.ouaf.system.keystore.mode - KeyStore Mode

Parameter	com.oracle.ouaf.system.keystore.mode
Description	Padding mode used within keystore
Ordinality	Mandatory
Valid Values	Generated using the KS_MODE parameter.
Source	Maintained by product templates. Use custom templates to implement a different value.
Applicability	BATCH
Example	com.oracle.ouaf.system.keystore.mode=CBC

A.6.5 com.oracle.ouaf.system.keystore.padding - KeyStore Padding Algorithm

Parameter	com.oracle.ouaf.system.keystore.padding
Description	Padding algorithm used within keystore
Ordinality	Mandatory
Valid Values	Generated using the KS_PADDING parameter.
Source	Maintained by product templates. Use custom templates to implement a different value.
Applicability	BATCH
Example	com.oracle.ouaf.system.keystore.padding=PKCS5Padding

A.6.6 com.oracle.ouaf.system.keystore.passwordFileName - KeyStore File

Parameter	com.oracle.ouaf.system.keystore.passwordFileName
Description	Location and name of keystore password file.
Ordinality	Mandatory
Valid Values	Generated using the KS_STOREPASS_FILE parameter.
Source	Maintained by product templates. Use custom templates to implement a different value.
Applicability	BATCH
Example	com.oracle.ouaf.system.keystore.passwordFileName =/scratch/OUAF/ks/.ouaf_storepass

A.6.7 com.oracle.ouaf.system.keystore.type - KeyStore Type

Parameter	com.oracle.ouaf.system.keystore.type
Description	Type of keystore.
Ordinality	Mandatory
Valid Values	Generated using the KS_STORETYPE parameter.
Source	Maintained by product templates. Use custom templates to implement a different value.
Applicability	BATCH
Example	com.oracle.ouaf.system.keystore.type=JCEKS

A.6.8 com.ouaf.batch.jvmoptions - JVM Options

Parameter	com.ouaf.batch.jvmoptions
Description	Custom JVM Options for submitter. Note: This setting can be overridden using the -z option on the submitjob[.sh]command line.
Ordinality	Mandatory
Valid Values	Valid JVM Options for the Java version used
Source	Maintained by product templates. Use bedit to implement a different value.
Applicability	BATCH
Example	com.ouaf.batch.jvmoptions=-Xms1024k -Xmx2048k -XX:MaxPermSize=512m

A.6.9 com.splwg.grid.executionMode - Mode of Execution

Parameter	com.splwg.grid.executionMode
Description	Execution Mode used by process.
	Note: This setting can be overridden using the -e option on the submitjob[.sh] command line.
Ordinality	Mandatory
Valid Values	[CLUSTERED THIN]
	Note: The THIN mode is used by the Oracle Utilities SDK and should not be used outside that tool.
Source	Maintained by product templates. Use custom templates to implement a different value.
Applicability	BATCH
Example	com.splwg.grid.executionMode=CLUSTERED

A.6.10 com.splwg.batch.submitter - THIN Submitter

Parameter	com.splwg.batch.submitter
Description	Whether this execution can run without a threadpoolworker. Reserved for development of batch using the Oracle Utilities SDK. If set to true then, com.splwg.grid.executionMode must be set to THIN.
Ordinality	Mandatory
Valid Values	[false true]
Source	Maintained by product templates for LOCAL submission.
Applicability	BATCH
Example	com.splwg.batch.submitter=true

A.6.11 com.splwg.batch.submitter.batchCd - Batch Code

Parameter	com.splwg.batch.submitter.batchCd
Description	<p>Batch Code for batch specific configuration. This setting should not be set in the global submitbatch.properties file.</p> <p>Note: This setting should only be set in configuration files for testing purposes. In other situations the -b option on the submitjob[.sh] command line should be used.</p>
Ordinality	Mandatory
Valid Values	Batch Code
Source	Maintained by product templates for submission.
Applicability	BATCH
Example	com.splwg.batch.submitter.batchCd=QABATCH

A.6.12 com.splwg.batch.submitter.distThreadPool - Threadpool

Parameter	com.splwg.batch.submitter.distThreadPool
Description	<p>Name of pool to be used for batch process. If threadpoolworker not used then LOCAL must be specified.</p> <p>This can be set globally and at the individual batch job level.</p> <p>Note: This setting can be overridden using the -p option on the submitjob[.sh] command line.</p>
Ordinality	Mandatory
Valid Values	Default: DEFAULT
Source	Maintained by product templates. Use custom templates to implement a different value.
Applicability	BATCH
Example	com.splwg.batch.submitter.distThreadPool=DEFAULT

A.6.13 com.splwg.batch.submitter.languageCd - Language Code

Parameter	com.splwg.batch.submitter.languageCd
Description	<p>Language code used for messages for execution of background process. Relevant language pack must be installed.</p> <p>Note: This setting can be overridden using the -l option on the submitjob[.sh] command line.</p>
Ordinality	Mandatory
Valid Values	Default:ENG
Source	Maintained by product templates. Use custom templates to implement a different value.
Applicability	BATCH
Example	com.splwg.batch.submitter.languageCd=ENG

A.6.14 com.splwg.batch.submitter.maximumCommitRecords - Commit Interval

Parameter	com.splwg.batch.submitter.maximumCommitRecords
Description	<p>Commit Interval used for execution. This is the number of objects processed per work unit.</p> <p>Note: This setting can be overridden using the -f option on the submitjob[.sh] command line.</p>
Ordinality	Mandatory
Valid Values	Job specific
Source	Maintained by product templates. Use custom templates to implement a different value.
Applicability	BATCH
Example	com.splwg.batch.submitter.maximumCommitRecords=200

A.6.15 com.splwg.batch.submitter.promptForValues - Prompt for Values

Parameter	com.splwg.batch.submitter.promptForValues
Description	<p>Prompt for value when running in interactive mode. This is primarily used for developers who are testing their job manually.</p> <p>Note: Implementers should only use the true value if executing jobs from the Oracle Utilities SDK.</p>
Ordinality	Mandatory
Valid Values	[true false]
Source	Maintained by product templates. Use custom templates to implement a different value.
Applicability	BATCH
Example	com.splwg.batch.submitter.promptForValues=false

A.6.16 com.splwg.batch.submitter.processDate - Business Date

Parameter	com.splwg.batch.submitter.processDate
Description	<p>Business Date for batch process. This setting should not be set in the global submitbatch.properties file.</p> <p>Note: This setting should only be set in configuration files for testing purposes. In other situations the -d option on the submitjob[.sh] command line should be used.</p>
Ordinality	Mandatory
Valid Values	Business Date in ISO YYYY-MM-DD format
Source	Maintained by product templates for submission.
Applicability	BATCH
Example	com.splwg.batch.submitter.processDate=2015-03-08

A.6.17 com.splwg.batch.submitter.rerunNumber - Re Run Number

Parameter	com.splwg.batch.submitter.rerunNumber
Description	Rerun Number to be used for execution.
	<p>Note:</p> <p>Only batch controls that support rerun numbers are supported with this configuration setting.</p> <p>This setting can be overridden using the -r option on the submitjob[.sh] command line.</p>
Ordinality	Optional
Valid Values	Valid run number. A value of zero (0) denotes disables this setting.
Source	Maintained by product templates. Use custom templates to implement a different value.
Applicability	BATCH
Example	com.splwg.batch.submitter.rerunNumber=56

A.6.18 com.splwg.batch.submitter.softParameter - Job Parameters

Parameter	com.splwg.batch.submitter.softParameter
Description	<p>For any program-specific parameters, use this form of property specification in the format: com.splwg.batch.submitter.softParameter.<parmname>=<value></p> <p>The <parmname> denotes the name of the parameter. For example, to specify a number of rows to skip when submitting a validation program:</p> <p>com.splwg.batch.submitter.softParameter.SKIP-ROWS=1000</p> <p>Multiple soft parameters may be specified.</p>
	<p>Note: This setting can be overridden using the -x or -X options on the submitjob[.sh] command line.</p>
Ordinality	Mandatory
Valid Values	Valid value for parameter
Source	Maintained by product templates for submission.
Applicability	BATCH
Example	com.splwg.batch.submitter.softParameter.SKIP-ROWS=1000

A.6.19 com.splwg.batch.submitter.threadCount - Thread Limit

Parameter	com.splwg.batch.submitter.threadCount
Description	Thread limit used for execution.
	<p>Note:</p> <p>Only batch controls that support multithreaded are supported with this configuration setting.</p> <p>This setting can be overridden using the -c option on the submitjob[.sh] command line.</p>
Ordinality	Mandatory
Valid Values	Valid thread limit. A value of one (1) is used for single threaded jobs. Default: 1
Source	Maintained by product templates. Use custom templates to implement a different value.
Applicability	BATCH
Example	com.splwg.batch.submitter.threadCount=1

A.6.20 com.splwg.batch.submitter.threadNumber - Thread Number

Parameter	com.splwg.batch.submitter.threadNumber
Description	Individual thread number used for execution.
	<p>Note: This setting can be overridden using the -t option on the submitjob[.sh] command line.</p>
Ordinality	Mandatory
Valid Values	Valid thread number. The value must be less than or equal to the com.splwg.batch.submitter.threadCount. A value of zero (0) spawns multiple threads up to the limit expressed in com.splwg.batch.submitter.threadCount. Default: 0
Source	Maintained by product templates. Use custom templates to implement a different value.
Applicability	BATCH
Example	com.splwg.batch.submitter.threadNumber=0

A.6.21 com.splwg.batch.submitter.traceProgramEnd - Trace Program End

Parameter	com.splwg.batch.submitter.traceProgramEnd
Description	Enables or disables tracing for the end of the program.
	<p>Note:</p> <p>This setting is designed for developers and for support purposes.</p> <p>This setting can be overridden using the -g option on the submitjob[.sh] command line.</p>
Ordinality	Mandatory
Valid Values	[true false]
Source	Maintained by product templates for submission.
Applicability	BATCH
Example	com.splwg.batch.submitter.traceProgramEnd=false

A.6.22 com.splwg.batch.submitter.traceProgramStart - Trace Program Start

Parameter	com.splwg.batch.submitter.traceProgramStart
Description	Enables or disables tracing for the start of the program.
	<p>Note: This setting is designed for developers and for support purposes.</p> <p>This setting can be overridden using the -g option on the submitjob[.sh] command line.</p>
Ordinality	Mandatory
Valid Values	[true false]
Source	Maintained by product templates for submission.
Applicability	BATCH
Example	com.splwg.batch.submitter.traceProgramStart=false

A.6.23 com.splwg.batch.submitter.traceSQL - Trace SQL Statements

Parameter	com.splwg.batch.submitter.traceSQL
Description	Enables or disables tracing of ALL SQL statements executed by the program.
	<p>Note:</p> <p>This setting is designed for developers and for support purposes.</p> <p>This setting can be overridden using the -g option on the submitjob[.sh] command line.</p>
Ordinality	Mandatory
Valid Values	[true false]
Source	Maintained by product templates for submission.
Applicability	BATCH
Example	com.splwg.batch.submitter.traceSQL=false

A.6.24 com.splwg.batch.submitter.traceStandardOut - Trace Output Statements

Parameter	com.splwg.batch.submitter.traceStandardOut
Description	Enables or disables tracing of ALL in-program debug statements executed by the program.
	<p>Note: This setting is designed for developers and for support purposes.</p> <p>This setting can be overridden using the -g option on the submitjob[.sh] command line.</p>
Ordinality	Mandatory
Valid Values	[true false]
Source	Maintained by product templates for submission.
Applicability	BATCH
Example	com.splwg.batch.submitter.traceStandardOut=false

A.6.25 com.splwg.batch.submitter.userId - Security User

Parameter	com.splwg.batch.submitter.userId
Description	<p>UserID used by job to check authorization to underlying application services.</p> <p>Note: This setting can be overridden using the -u option on the submitjob[.sh] command line.</p>
Ordinality	Mandatory
Valid Values	<p>Valid userID.</p> <p>Note: The SYSUSER account should not be used for non-demonstration environments.</p>
Source	Maintained by product templates. Use custom templates to implement a different value.
Applicability	BATCH
Example	com.splwg.batch.submitter.userId=USER01

A.6.26 `spl.runtime.batch.L2CacheMode` - L2 Cache Control

Parameter	<code>spl.runtime.batch.L2CacheMode</code>
Description	<p>Defines the 2nd-level cache mode. Valid values are READ_ONLY (default), READ_WRITE or OFF.</p> <ul style="list-style-type: none"> • READ_ONLY is for performance as it loads the configuration entities into the 2nd-level (JVM-level) cache and accesses them from there itself. In READ_ONLY mode, the cached entities may not be updated. • READ_WRITE also loads them into the L2 cache, but they can be updated. The drawback is that an update of a cached entity hits both the database and cache as it gets updated in both places. • In OFF mode the 2nd-level cache is completely disabled. Some jobs, for example LDAP import (F1-LDAP), need to update some of these entities (e.g. User), so it requires the L2 cache to be either OFF or READ_WRITE. The choice between OFF and READ_WRITE depends on requirement; the effect is the same. <p>Note: This setting can be overridden using the -l2 option on the submitjob[.sh] command line.</p>
Ordinality	Mandatory
Valid Values	[READ_ONLY READ_WRITE OFF]
Source	Maintained by product templates for submission.
Applicability	BATCH
Example	<code>spl.runtime.batch.L2CacheMode=READ_ONLY</code>

A.6.27 tangosol.coherence.distributed.localstorage - Cache Mode

Parameter	tangosol.coherence.distributed.localstorage
Description	Sets whether data is cached local or not. This is used to optimize large networks of submitters and threadpools with cache nodes.
Ordinality	Mandatory
Valid Values	[false true]
Source	Maintained by product templates. Use custom templates to implement a different value.
Applicability	BATCH
Example	tangosol.coherence.distributed.localstorage=false

A.6.28 tangosol.coherence.role - Submitter Role

Parameter	tangosol.coherence.role
Description	Sets role of Submitter. Informational information on JVM used for monitoring purposes only.
Ordinality	Optional
Valid Values	Generated with the name OUAF_<batchcode>_Submitter where <batchcode> is the Batch Control identifier for the batch job.
Source	Maintained by product templates. Use custom templates to implement a different value.
Applicability	BATCH
Example	tangosol.coherence.role=OUAF_QABATCH_Submitter

A.7 threadpoolworker.properties

This configuration sets the threadpoolworker configuration for global and individual threadpoolworkers. As with submitters there are global defaults as well as individual threadpoolworker configurations.

Note:

Some settings in this file are shared with the submitbatch.properties file but these settings apply to the threadpoolworker JVM's rather than submitter JVM's.

This section is the default set of configuration parameters. Additional Oracle Coherence parameters can be added using custom templates.

A.7.1 com.oracle.ouaf.batch.scriptDir - Base Scripts

Directory for Infrastructure Job

Parameter	com.oracle.ouaf.batch.scriptDir
Description	The base directory in which the scripts have to be placed for the generic infrastructure job to execute them.
Ordinality	Optional
Valid Values	Directory path.
Source	Defaulted by configureEnv.
Applicability	BATCH
Example	com.oracle.ouaf.batch.scriptDir=\$SPLBASE/scripts/generic/batch/exposed/\$OWNER \$OWNER would be the owner flag of the batch control thereby allowing restrictions on which scripts might be executed. Additional owners can be provided access by creating symbolic links in those owners' directories.

A.7.2 com.oracle.ouaf.system.keystore.alias -

Threadpoolworker KeyStore Alias

Parameter	com.oracle.ouaf.system.keystore.alias
Description	Alias used within keystore for threadpoolworker.
Ordinality	Mandatory
Valid Values	Generated using the KS_ALIAS parameter.
Source	Maintained by product templates. Use custom templates to implement a different value.

Applicability	BATCH
Example	com.oracle.ouaf.system.keystore.alias=thealias

A.7.3 com.oracle.ouaf.system.keystore.file - Threadpoolworker KeyStore File

Parameter	com.oracle.ouaf.system.keystore.file
Description	Location and name of keystore file for encryption keys for threadpoolworker.
Ordinality	Mandatory
Valid Values	Generated using the KS KEYSTORE FILE parameter.
Source	Maintained by product templates. Use custom templates to implement a different value.
Applicability	BATCH
Example	com.oracle.ouaf.system.keystore.file =/scratch/OUAF/ks/.ouaf_keystore

A.7.4 com.oracle.ouaf.system.keystore.hmac_key_alias - Threadpoolworker KeyStore HMAC Key Alias

Parameter	com.oracle.ouaf.system.keystore.hmac_key_alias
Description	HMAC Alias used within keystore for threadpoolworker
Ordinality	Mandatory
Valid Values	Generated using the KS HMAC ALIAS parameter.
Source	Maintained by product templates. Use custom templates to implement a different value.
Applicability	BATCH
Example	com.oracle.ouaf.system.keystore.hmac_key_alias=thealiasHMAC

A.7.5 com.oracle.ouaf.system.keystore.mode - Threadpoolworker KeyStore Mode

Parameter	com.oracle.ouaf.system.keystore.mode
Description	Padding mode used within keystore for threadpoolworker
Ordinality	Mandatory
Valid Values	Generated using the KS MODE parameter.
Source	Maintained by product templates. Use custom templates to implement a different value.
Applicability	BATCH
Example	com.oracle.ouaf.system.keystore.mode=CBC

A.7.6 com.oracle.ouaf.system.keystore.padding - Threadpoolworker KeyStore Padding Algorithm

Parameter	com.oracle.ouaf.system.keystore.padding
Description	Padding mode used within keystore for threadpoolworker
Ordinality	Mandatory
Valid Values	Generated using the KS_PADDING parameter.
Source	Maintained by product templates. Use custom templates to implement a different value.
Applicability	BATCH
Example	com.oracle.ouaf.system.keystore.padding=PKCS5Padding

A.7.7 com.oracle.ouaf.system.keystore.passwordFileName - Threadpoolworker KeyStore File

Parameter	com.oracle.ouaf.system.keystore.passwordFileName
Description	Location and name of keystore password file for threadpoolworker.
Ordinality	Mandatory
Valid Values	Generated using the KS_STOREPASS_FILE parameter.
Source	Maintained by product templates. Use custom templates to implement a different value.
Applicability	BATCH
Example	com.oracle.ouaf.system.keystore.passwordFileName =/scratch/OUAF/ks/.ouaf_storepass

A.7.8 com.oracle.ouaf.system.keystore.type - Threadpoolworker KeyStore Type

Parameter	com.oracle.ouaf.system.keystore.type
Description	Type of keystore for threadpoolworker.
Ordinality	Mandatory
Valid Values	Generated using the KS_STORETYPE parameter.
Source	Maintained by product templates. Use custom templates to implement a different value.
Applicability	BATCH
Example	com.oracle.ouaf.system.keystore.type=JCEKS

A.7.9 com.ouaf.batch.disableAutoFlush – Auto Flush Batch L2 Cache

Parameter	com.ouaf.batch.disableAutoFlush
Description	Disables the auto flushing of batch L2 cache. If this value is set to true, the L2 cache auto flush will be disabled.
Ordinality	Mandatory
Valid Values	[true false]. Default value is false.
Source	Generated by template. Use bedit to implement a different value.
Applicability	BAS
Example	com.ouaf.batch.disableAutoFlush=true

A.7.10 com.ouaf.batch.flushIntervalInSeconds – Batch L2 Cache Auto Flush Interval

Parameter	com.ouaf.batch.flushIntervalInSeconds
Description	Sets the time interval between batch L2 cache auto flushes. The time interval should be specified in seconds. Default value is 60.
Ordinality	Optional
Valid Values	Value in seconds. Default is 60.

Source	Generated by template. Use bedit to implement a different value.
Applicability	BAS
Example	com.ouaf.batch.flushIntervalInSeconds=90

A.7.11 com.ouaf.batch.jvmoptions - Threadpool JVM Options

Parameter	com.ouaf.batch.jvmoptions
Description	Custom JVM Options for threadpool. Note: This setting can be overridden using the <code>-z</code> option on the threadpoolworker[.sh] command line.
Ordinality	Mandatory
Valid Values	Valid JVM Options for the Java version used
Source	Maintained by product templates. Use bedit to implement a different value.
Applicability	BATCH
Example	com.ouaf.batch.jvmoptions=-Xms1024k-Xmx2048k-XX:MaxPermSize=512m

A.7.12 com.splwg.grid.executionMode - Threadpool Mode of Execution

Parameter	com.splwg.grid.executionMode
Description	<p>Execution Mode used by this threadpool.</p> <p>Note: This setting can be overridden using the <code>-e</code> option on the threadpoolworker[.sh] command line.</p>
Ordinality	Mandatory
Valid Values	[CLUSTERED]
Source	Maintained by product templates.
Applicability	BATCH
Example	com.splwg.grid.executionMode=CLUSTERED

A.7.13 com.splwg.grid.distThreadPool.threads - Threadpool Thread Limit

Parameter	com.splwg.grid.distThreadPool.threads
Description	<p>Maximum number of threads for a particular threadpool.</p> <p>The format of the setting is:</p> <p><code>com.splwg.grid.distThreadPool.threads.<poolname>=<limit></code></p> <p>where:</p> <p><poolname> is the Name of the Threadpool <limit> is the thread limit supported by each instance of the Threadpool</p> <p>Note: This setting can be overridden using the <code>-p</code> option on the threadpoolworker[.sh] command line.</p>
Ordinality	Mandatory
Valid Values	Threadpool names and limit must be valid
Source	Maintained by product templates. Use bedit to implement a different value.
Applicability	BATCH
Example	com.splwg.grid.distThreadPool.threads.DEFAULT=5

A.7.14 com.splwg.batch.scheduler.daemon - Scheduler Daemon

Parameter	com.splwg.batch.scheduler.daemon
Description	<p>Configures whether the threadpool should execute the online scheduler daemon. The online scheduler daemon checks that the Batch Submission transaction and initiates execution of pending batch jobs.</p> <p>Note:</p> <p>This setting can be overridden using the –d option on the threadpoolworker[.sh] command line.</p> <p>This setting should only be set to true in non-Production environment where online submission is enabled.</p> <p>In any non-Production environment that uses online submission; one threadpool should have this setting enabled. Typically this is the DEFAULT threadpool but can be any other threadpool.</p>
Ordinality	Mandatory
Valid Values	[true false]
Source	Maintained by product templates. Use bedit to implement a different value.
Applicability	BATCH
Example	com.splwg.batch.scheduler.daemon=false

A.7.15 `oracle.ouaf.jmx.remote.maxPortsToTry` - Ports to Attempt to Connect to

Parameter	<code>oracle.ouaf.jmx.remote.maxPortsToTry</code>
Description	<p>Number of ports to try starting from either oracle.ouaf.jmx.remote.startPort or spl.runtime.management.rmi.port.</p> <p>If oracle.ouaf.jmx.remote.startPort is not specified, the property <code>spl.runtime.management.rmi.port</code> is used that as the starting port. If neither property is defined or the maximum number of ports to try has been reached, an exception will be thrown that will prevent the system from starting</p>
Ordinality	Optional
Valid Values	Number. Default: 200
Source	Set by BATCH_RMI_PORT . Use bedit to implement a different value.
Applicability	BATCH
Example	<code>oracle.ouaf.jmx.remote.maxPortsToTry=100</code>

A.7.16 `oracle.ouaf.jmx.remote.startPort` - Override Batch JMX Port

Parameter	<code>oracle.ouaf.jmx.remote.startPort</code>
Description	Alternative Port number allocated for Batch JMX facility. This value is typically the same as spl.runtime.management.rmi.port . But may be set to the Coherence JMX port if Coherence based JMX is used on a different port
Ordinality	Optional
Valid Values	Valid JMX Port
Source	Set by BATCH_RMI_PORT . Use bedit to implement a different value.
Applicability	BATCH
Example	<code>oracle.ouaf.jmx.remote.startPort=6510</code>

A.7.17 ouaf.batch.onlineLogDir - Online Line Batch Log Directory

Parameter	ouaf.batch.onlineLogDir
Description	Sets the location of output from online batch submission and batch scheduler integration. If this property is set, batch logs will be accessible via the Batch Run Tree (application UI). Otherwise, the batch logs download link in the application will be disabled.
Ordinality	Optional
Valid Values	Valid location. Defaults to: \$SPLOUTPUT (%SPLOUTPUT% on Windows)
Source	Value inherited from BATCH_ONLINE_LOG_DIR from ENVIRON.INI.
Applicability	BATCH
Example	ouaf.batch.onlineLogDir=/tmp

A.7.18 ouaf.batch.onlineLogDir.retain – Retain Online Line Batch Log Files

Parameter	ouaf.batch.onlineLogDir.retain
Description	Sets the total number of log files that are to be stored for each batch code and thread number. The log files for the particular batch code and thread number will be deleted except for the latest number of logs specified.
Ordinality	Optional
Valid Values	Number
Source	Generated by template. Use bedit to implement a different value.
Applicability	BATCH
Example	ouaf.batch.onlineLogDir.retain=3 The above example will keep the last three logs and delete the rest.

A.7.19 spl.runtime.batch.disableDeferredKeyInserts - Deferred Key Inserts

Parameter	spl.runtime.batch.disableDeferredKeyInserts
Description	Whether the deferring of key insert in batches should be disabled or not. Enables (false) or disables (true) deferred Key Inserts.

	<p>The default is to use deferred inserts. However if an aggressive key insert is desired in batches, a value of true should be used.</p> <p>Note: This setting is used by particular base batch jobs. Refer to the online documentation for individual batch jobs for more information.</p>
Ordinality	Mandatory
Valid Values	[true false]
Source	Generated by template, Use bedit to implement a different value.
Applicability	BATCH
Example	<code>spl.runtime.batch.disableDeferredKeyInserts=false</code>

A.7.20 `spl.runtime.batch.L2CacheMode` - Threadpoolworker L2 Cache Control

Parameter	<code>spl.runtime.batch.L2CacheMode</code>
Description	<p>Defines the 2nd-level cache mode for threads in threadpool. Valid values are READ_ONLY (default), READ_WRITE or OFF.</p> <ul style="list-style-type: none"> • READ_ONLY is for performance as it loads the configuration entities into the 2nd-level (JVM-level) cache and accesses them from there itself. In READ_ONLY mode, the cached entities may not be updated. • READ_WRITE also loads them into the L2 cache, but they can be updated. The drawback is that an update of a cached entity hits both the database and cache as it gets updated in both places. • In OFF mode the 2nd-level cache is completely disabled. Some jobs, for example LDAP import (F1-LDAP), need to update some of these entities (e.g. User), so it requires the L2 cache to be either OFF or READ_WRITE. The choice between OFF and READ_WRITE depends on requirement; the effect is the same. <p>Note: This setting can be overridden using the -l2 option on the threadpoolworker[.sh] command line.</p>
Ordinality	Mandatory
Valid Values	[READ_ONLY READ_WRITE OFF]
Source	Maintained by product templates for threadpoolworker. Use bedit to implement a different value.
Applicability	BATCH
Example	<code>spl.runtime.batch.L2CacheMode=READ_ONLY</code>

A.7.21 `spl.runtime.management.connector.url.default` - Batch JMX URL

Parameter	<code>spl.runtime.management.connector.url.default</code>
Description	JMX URL for Batch JMX interface.
	Note: This URL is generated and should not be altered.
Ordinality	Optional
Valid Values	Valid JMX URL
Source	Generated by template.
Applicability	BATCH
Example	<pre>spl.runtime.management.connector.url.default= service:jmx:rmi:///jndi/rmi:///{host}:{port} /oracle/ouaf/batchConnector</pre>

A.7.22 `spl.runtime.management.rmi.port` - Batch JMX Port

Parameter	<code>spl.runtime.management.rmi.port</code>
Description	Port number allocated for Batch JMX facility.
	Note: This setting can be overridden using the <code>-i</code> option on the threadpoolworker[.sh] command line.
Ordinality	Optional
Valid Values	Valid JMX Port
Source	Set by BATCH_RMI_PORT . Use bedit to implement a different value.
Applicability	BATCH
Example	<code>spl.runtime.management.rmi.port=1001</code>

A.7.23 tangosol.coherence.distributed.localstorage - DistributedCache Storage

Parameter	tangosol.coherence.distributed.localstorage
Description	Specifies whether this member of the DistributedCache service enables local storage. Note: This setting is used by the Oracle Coherence DistributedCache Service.
Ordinality	Optional
Valid Values	[true false]
Source	Generated by template, Use bedit to implement a different value.
Applicability	BATCH
Example	tangosol.coherence.localport.adjust=true

A.7.24 tangosol.coherence.distributed.threads - Internal Cache Threads

Parameter	tangosol.coherence.distributed.threads
Description	Specifies the number of daemon threads used by the distributed cache service. Note: This setting is used by the Oracle Coherence DistributedCache Service.
Ordinality	Optional
Valid Values	Valid thread numbers. Default: 0
Source	Generated by template, Use bedit to implement a different value.
Applicability	BATCH
Example	tangosol.coherence.distributed.threads=4

A.7.25 tangosol.coherence.invocation.threads - Internal Invocation Threads

Parameter	tangosol.coherence.invocation.threads
Description	Specifies the number of daemon threads to be used by the invocation service. If zero, all relevant tasks are performed on the service thread.
	Note: This setting is used by the Oracle Coherence InvocationService.
Ordinality	Optional
Valid Values	Valid thread numbers. Default: 0
Source	Generated by template, Use bedit to implement a different value.
Applicability	BATCH
Example	tangosol.coherence.invocation.threads=4

A.7.26 tangosol.coherence.localhost - Unicast Host Address

Parameter	tangosol.coherence.localhost
Description	Host name for local host for Unicast address.
	Note: This setting applies to unicast or well known address implementation . This setting is used by the Oracle Coherence unicast-listener.
Ordinality	Optional
Valid Values	Valid host name defined in hosts file and/or DNS
Source	Generated by template (wka only). Use bedit to implement a different value.
Applicability	BATCH
Example	tangosol.coherence.localhost=myserver.example.com

A.7.27 tangosol.coherence.localport - Unicast Port

Parameter	tangosol.coherence.localport
Description	Port number for local host for Unicast address.
	<p>Note:</p> <p>This setting applies to unicast or well known address implementation.</p> <p>This setting is used by the Oracle Coherence unicast-listener.</p>
Ordinality	Optional
Valid Values	Valid port number
Source	Generated by template. Use bedit to implement a different value.
Applicability	BATCH
Example	tangosol.coherence.localport=6570

A.7.28 tangosol.coherence.localport.adjust - Unicast Port Adjustment

Parameter	tangosol.coherence.localport.adjust
Description	Specifies whether the unicast port is automatically incremented if the specified port cannot be bound to because it is in use.
	<p>Note:</p> <p>This setting applies to unicast or well known address implementation.</p> <p>This setting is used by the Oracle Coherence unicast-listener.</p>
Ordinality	Optional
Valid Values	[true false]
Source	Generated by template (wka only). Use bedit to implement a different value.
Applicability	BATCH
Example	tangosol.coherence.localport.adjust=true

A.7.29 tangosol.coherence.role - Threadpoolworker Role

Parameter	tangosol.coherence.role
Description	This contains the name of the member role. This name allows an application to organize members into specialized roles, such as cache servers and cache clients. The name is also useful for displaying management information (for example, JMX) and interpreting log entries.
	Note: This setting is used by the Oracle Coherence member-identity.
Ordinality	Optional
Valid Values	Role Name
Source	Generated by template. Use bedit to implement a different value.
Applicability	BATCH
Example	tangosol.coherence.role=OUAF_Base_TPW

A.8 coherence-cache.config.xml

The coherence-cache.config.xml file is generated using the coherence-cache.config.xml.template located in the templates directory.

The format and structure are setup for the implementation of Oracle Coherence for the batch infrastructure within the product.

Note: This file is fixed in format and should not be altered unless instructed by Oracle Support.

A.9 tangosol-coherence-override.xml

The tangosol-coherence-override.xml file is generated using the templates located in the templates directory.

There are four templates for this file:

Template	Contents
tangosol-coherence-override.mc.be.template	Multicast Overrides (for bedit)
tangosol-coherence-override.ss.be.template	Single Server Overrides (for bedit)
tangosol-coherence-override.wka.be.template	WKA Overrides (for bedit)
tangosol-coherence-override.xml.template	General Overrides

The format and structure are setup for the implementation of Oracle Coherence for the batch infrastructure within the product.

Note: This file is fixed in format and should not be altered unless instructed by Oracle Support.