Oracle Financial Services Revenue Management and Billing

OR

Oracle Insurance Revenue Management and Billing

Version 6.1.0.0.0

Server Administration Guide

Revision 24.0

F88965-01

January 2024



Oracle Financial Services Revenue Management and Billing/Oracle Insurance Revenue Management and Billing Server Administration Guide

Note: To improve the content readability, the above two products are collectively referred to as Oracle Revenue Management and Billing throughout this document.

F88965-01

Copyright Notice

Copyright © 2009, 2024, Oracle and/or its affiliates.

License Restrictions

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or de-compilation of this software, unless required by law for interoperability, is prohibited.

Warranty Disclaimer

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

Restricted Rights Notice

If this is software, software documentation, data (as defined in the Federal Acquisition Regulation), or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs) and Oracle computer documentation or other Oracle data delivered to or accessed by U.S. Government end users are "commercial computer software," "commercial computer software documentation," or "limited rights data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, reproduction, duplication, release, display, disclosure, modification, preparation of derivative works, and/or adaptation of i) Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs), ii) Oracle computer documentation and/or iii) other Oracle data, is subject to the rights and limitations specified in the license contained in the applicable contract. The terms governing the U.S. Government's use of Oracle cloud services are defined by the applicable contract for such services. No other rights are granted to the U.S. Government.

Hazardous Applications Notice

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Trademark Notice

Oracle, Java, MySQL, and NetSuite are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Inside are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Epyc, and the AMD logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

Third-Party Content, Products, and Services Disclaimer

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

Preface

About This Document

This document helps you to understand the Oracle Revenue Management and Billing (ORMB) architecture and the concepts required for configuring and using the ORMB application. It explains how to configure and deploy web and business application servers. In addition, it explains how to monitor client machines, web and/or business application servers, and database connections.

Note:

All examples and screen captures are used for publishing purposes only and may vary from the actual values seen at your site.

This document covers Oracle Utilities Application Framework V4.5.0.1.1.

For publishing purposes, the Oracle Revenue Management and Billing product will be referred to as "product" in this document.

Sections of this manual cover the background processing (also known as batch) aspects of the Oracle Utilities Application Framework for completeness only.

This document now covers aspects of the bundling of Oracle Service Bus and SOA infrastructure. The relevant settings for this component are marked with OSB and SOA acronyms. Not all products use the Oracle Service Bus and SOA infrastructure natively; please refer to the installation guide for clarification. Refer to the *Oracle SOA Suite* documentation for more information about these products.

Intended Audience

This document is intended for the following audience:

- System and Database Administrators
- Consulting Team
- Implementation Team

Organization of the Document

The information in this document is organized into the following sections:

Section No.	Section Name	Description
Section 1	Architecture	Describes the architecture of the Oracle Revenue Management and Billing application. It also lists the roles and features of each component.
Section 2	Concepts	Lists and describes the concepts which you need to understand before configuring and using the Oracle Revenue Management and Billing application.

Section No.	Section Name	Description
Section 3	Operations	Lists and describes various command line utilities. It also explains how to start and stop the Oracle Revenue Management and Billing environments.
Section 4	Monitoring	Lists and describes the basic monitoring regimes and methods used for the Oracle Revenue Management and Billing application. It also explains how to monitor client machines, web and/or business application servers, and database connections.
Section 5	Configuration	Lists and describes various configuration files available in the Oracle Revenue Management and Billing application. It explains how to configure and deploy web and business application servers. In addition, it explains how to configure Web browser, inbound web services, and batch server.
Section 6	Miscellaneous Operations and Configuration	Lists and describes additional configurations that you may want to perform based on the requirement.
Section 7	Operations from Oracle Enterprise Manager	Lists Oracle Utilities targets which are available for the Oracle Revenue Management and Billing application. It explains how to discover Oracle Utilities and Oracle WebLogic targets. It also explains how to monitor the application using Oracle Enterprise Manager.
Section 8	Oracle Scheduler Integration	Provides an overview for Oracle Scheduler Interface. It explains how to create schedule jobs using Oracle Scheduler, execute or cancel the schedule jobs, and how to monitor Oracle Scheduler.

Section No.	Section Name	Description
Appendix A	Parameters	Lists and describes the parameters of various configuration files, such as:
		environ.ini
		• web.xml
		spl.properties
		 hibernate.properties
		 submitbatch.properties
		 threadpoolworker.properties
		 coherence-cache.config.xml
		 tangosol-coherence-override.xml
		It also describes the JEE filters that you can use
		in the Oracle Revenue Management and Billing
		application.

Acronyms

The following acronyms are used in this document:

Acronym	Meaning
ORMB	Oracle Revenue Management and Billing
OUAF	Oracle Utilities Application Framework
WAS	Web Application Server
BAS	Business Application Server
BUI	Browser User Interface
JVM	Java Virtual Machine
JMX	Java Management Extensions
MBeans	JMX Management Beans
UCP	Universal Connection Pool
ORM	Object Relational Mapping
XAI	XML Application Integration
SaaS	Software as a Service
PaaS	Platform as a Service
WLDF	Oracle WebLogic Diagnostics Framework
ECID	Execution Context Identifier
RAC	Oracle Real Application Clustering

Acronym	Meaning
ONS	Oracle Notification Service
SCAN	Oracle Single Client Access Name
JMS	Java Message Services
EJB	Enterprise Java Beans
OMR	Oracle Management Repository
OMS	Oracle Management Server
ОМА	Oracle Management Agents
MDS	SOA Suite Meta Data Service
DPM	SOA Suite User Message Services
OSB	Oracle Service Bus
IWS	Inbound Web Services
НТТР	Hypertext Transfer Protocol
WSDL	Web Service Description Language
OPA	Open Policy Agent
CPU	Central Processing Unit
ВРА	Business Process Automation
UTF	Unicode Transformation Format
SDK	Software Development Kit
ENG	English
URL	Uniform Resource Locator
URI	Uniform Resource Identifier
API	Application Programming Interface

Related Documents

You can refer to the following documents for more information:

Document	Description
Oracle Revenue Management and Billing Version 6.1.0.0.0 Release Notes	Provides a brief description about the new features, enhancements, UI and database level changes, supported platforms, framework upgrade, supported upgrades, and technology upgrade made in this release. It also highlights the discontinued features, bug fixes, and known issues in this release.

Document	Description
Oracle Revenue Management and Billing Installation Guide	Lists the application server pre-requisites, supported platforms, and software and hardware requirements for installing the Oracle Revenue Management and Billing application. It explains how to install the Oracle Revenue Management and Billing application.
Oracle Revenue Management and Billing Quick Installation Guide	Provides high-level information on how to install the Oracle Revenue Management and Billing (ORMB) application and selected additional software.
Oracle Revenue Management and Billing Database Administrator's Guide	Provides information about the Oracle Database Server and Client required for installing the Oracle Revenue Management and Billing database. It explains how to install database with and without demo data. It provides database configuration guidelines including recommended settings for the Oracle Exadata Database machine.
Oracle Revenue Management and Billing Security Guide	Lists the security features available in the Oracle Revenue Management and Billing application. It explains how to configure security for the Oracle Revenue Management and Billing application using the default security features.

You can also refer to the following artifacts on My Oracle Support using the respective Document ID or part number:

- Native Installation Oracle Utilities Application Framework (Document ID: 1544969.1)
- <u>Environment Management document in the Software Configuration Management series</u> (Document ID: 560401.1)
- <u>Batch Best Practices</u> (Document ID: 836362.1)
- Software Configuration Management Series (Document ID: 560401.1)
- Oracle WebLogic JMS Integration (Document ID: 1308181.1)
- Migrating from XAI to IWS (Document ID: 1644914.1)
- Oracle Identity Manager Interface Configuration File (Document ID: 970785.1)
- Oracle Application Management Pack for Oracle Utilities Overview (Document ID: 1474435.1)

Access to Oracle Support

Oracle customers that have purchased support have access to electronic support through My Oracle Support. For information, visit http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info or visit http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs if you are hearing impaired.

Whitepapers

Several supplemental whitepapers are available for the Oracle Utilities Application Framework based products from My Oracle Support. At the time of publication, the following whitepapers are available on specific topics:

Whitepaper	Document ID
Technical Best Practices	<u>560367.1</u>
Performance Troubleshooting Guideline Series	<u>560382.1</u>
Software Configuration Management Series	560401.1
Security Overview	773473.1
LDAP Integration	774783.1
Interface Integration Overview	789060.1
Single Sign On Integration	799912.1
Architecture Guidelines	807068.1
Batch Best Practices	836362.1
What's New In Oracle Utilities Application Framework	<u>1177265.1</u>
Database Vault Integration	<u>1290700.1</u>
BI Publisher Integration Guidelines	1299732.1
Oracle SOA Suite Integration	1308161.1
Oracle WebLogic JMS Integration	1308181.1
Oracle Identity Management Suite Integration	<u>1375600.1</u>
Advanced Security Overview	<u>1375615.1</u>
Integration Reference Solutions	<u>1506855.1</u>
Oracle Service Bus Integration	<u>1558279.1</u>
Audit Vault Integration	<u>1606764.1</u>
Private Cloud Planning Guide	<u>1643845.1</u>
Migrating from XAI to IWS	1644914.1
ILM Planning Guide	1682436.1
ConfigTools Best Practices	1929040.1
Oracle Utilities Application Framework - Batch Scheduler Integration	2138193.1
Implementing Oracle In-Memory Option in Oracle Utilities Application Framework Products	<u>2404696.1</u>
Using Groovy Script in Oracle Utilities Applications	<u>2427512.1</u>

Note: Refer to My Oracle Support for any additional whitepapers.

Contents

1.	Arch	itecture.		1		
	1.1	Roles a	Roles and Features			
		1.1.1	Browser Client	3		
		1.1.2	Web Application Server	3		
		1.1.3	Business Application Server	4		
		1.1.4	Database Server	4		
		1.1.5	Batch Server	4		
2.	Cond	epts		8		
	2.1	Environment				
		2.1.1	Environment Identifier	8		
		2.1.2	Server Roles	9		
	2.2	Admini	istration User ID and Group	9		
	2.3	Native :	Support	10		
	2.4	Directo	ory Structure	11		
	2.5	Software Directory Structure				
		2.5.1	Software (splapp) Directory	13		
		2.5.2	Tools Directory	13		
		2.5.3	Directory Permissions	14		
	2.6			15		
	2.7	7 Environment Variables		15		
	2.8	S Common Application Logs				
	2.9	Batch Concepts				
		2.9.1	Batch Clustering Concepts			
		2.9.2	Batch Controls	20		
		2.9.3	Standard Parameters	20		
		2.9.4	Additional Key Parameters	22		
		2.9.5	Batch Run Tree	23		
		2.9.6	Timed Jobs	23		
		2.9.7	Level of Service	24		
		2.9.8	Explanation of Commit Interval	24		
		2.9.9	Explanation of Thread Limit and Thread Number	25		
		2.9.10	Explanation of Restart and Rerun	26		
		2.9.11	Submission Methods	26		
3.	Oper	rations		29		
	3.1 Command Line Utilities		29			
		3.1.1	bedit - Batch Edit	29		
		3.1.2	buildJavadocsIndex.sh - Builds Java Docs	30		
		3.1.3	configureEnv – Set up Environment Settings	31		
		3.1.4	createDBStandalone.sh - Creates Database Patches	32		
		3.1.5	extractCMSourceUNIX.sh - Migrate Code Across Upgrades	33		
		3.1.6	initialSetup – Maintain Configuration Settings	34		
		3.1.7	installSFGroup.sh - Install Software Patches	36		

		3.1.8	invokeDBUpdatePatch.sh - Regenerates Passwords in Installation Options	36
		3.1.9	iwsdeploy - Inbound Web Services Deployment	37
		3.1.10	jmxbatchclient.sh – JMX Batch Command Line	37
		3.1.11	ouafDatabasePatch.sh - Install Database Patches	39
		3.1.12	PatchDeployUtility.sh - Create and Deploy Patch Rollups	40
		3.1.13	showjavaproc.sh - Show Java Processes	41
		3.1.14	splenviron – Set Environment Variables	42
		3.1.15	starttpw.sh - Start Threadpoolworker	43
		3.1.16	submitbatchREST.sh - Submit Batch Threads through the REST API	44
		3.1.17	submitjob.sh - Submit Batch Threads (Legacy Method of BatchSubmission)	46
		3.1.18	threadpoolworker.sh - Manage Threadpools	49
	3.2	Starting	g and Stopping Using Consoles	51
4.	Mon	itoring		53
	4.1	Monito	oring Regimes	53
	4.2	Monito	pring Client Machines	54
		4.2.1	Monitoring the Desktop	54
		4.2.2	Client Debug Facility	55
	4.3	Monito	oring Web/Business Application Server	57
	4.4	JMX Ba	sed Monitoring	58
		4.4.1	Web Application Server JMX Reference	59
		4.4.2	Business Application Server JMX Reference	67
		4.4.3	Batch JMX Reference	70
		4.4.4	JMX Security	77
		4.4.5	Extending JMX Security	77
		4.4.6	Execution Dump Format	77
		4.4.7	Service Lists	78
		4.4.8	Resetting Statistics	79
	4.5	Database Connection Monitoring		79
	4.6	Probe Transaction		80
5.	Conf	nfiguration		81
	5.1	1 Configuration Files		81
		5.1.1	cistab - Global Configuration Files	81
		5.1.2	coherence-cache-config.xml - Oracle Coherence Configuration (BATCH)	82
		5.1.3	eOBatch.properties - General Batch Properties	82
		5.1.4	ejb-jar.xml - Enterprise Java Server Beans Configuration	82
		5.1.5	ENVIRON.INI - Environment Configuration File	82
		5.1.6	hibernate.properties - Database Connectivity Settings	84
		5.1.7	log4j2.properties – Product Logging Configuration	84
		5.1.8	Server Jar File (ouaf_jar_versions.txt)	85
		5.1.9	spl.properties – Product Behaviour Settings	85
		5.1.10	submitbatch.properties - Submitter Configuration (BATCH)	85
		5.1.11	tangosol-coherence-override.xml - Coherence Overrides (BATCH)	85
		5.1.12	threadpoolworker.properties - Threadpool Configuration (BATCH)	86
		5.1.13	web.xml – JEE Deployment Descriptor	86
		5.1.14	weblogic.xml – Oracle WebLogic Extensions	87
		5.1.15	weblogic-ejb-jar.xml – WebLogic Extensions for Enterprise Java Server Beans	89

	5.1.16	webservices.xml.resource - Web Services Configuration	89
5.2	Web Br	rowser Configuration	90
5.3	Web Application Server Configuration		
	5.3.1	Web Application Server Concepts	91
	5.3.2	Web Applications	91
	5.3.3	Web Application Server Configuration Files	92
	5.3.4	Web Application Server Configuration Process	93
	5.3.5	Quick Reference Guide for Web Application Server Configuration	95
	5.3.6	User Interface Backward Compatibility Settings	96
	5.3.7	Web Application Server Deployment Process	96
5.4	Busines	ss Application Server Configuration	97
	5.4.1	Business Application Server Concepts	99
	5.4.2	Business Application Server Configuration Files	99
	5.4.3	Business Application Server Configuration Process	100
	5.4.4	Quick Reference Guide for Business Application Server Configuration	102
	5.4.5	Business Application Server Deployment Process	103
5.5	Inboun	d Web Services Configuration	104
	5.5.1	Enabling Inbound Web Services	104
	5.5.2	Inbound Web Services Configuration Files	106
	5.5.3	Inbound Web Services Concepts	107
	5.5.4	Inbound Web Services Configuration Process	108
	5.5.5	Inbound Web Services Deployment Process	110
	5.5.6	Quick Reference Guide for Inbound Web Services Configuration	111
	5.5.7	Inbound Web Services Deployment Utilities	111
5.6	Batch S	Server Configuration	112
	5.6.1	Batch Configuration Files	112
	5.6.2	General Configuration Process	114
	5.6.3	Configuring Batch Using Bedit	115
	5.6.4	Batch Configuration Guidelines	122
	5.6.5	Batch Performance	125
5.7	Oracle	Cloud Support	126
	5.7.1	Support for Host Allow Listing	
	5.7.2	Support for URI Specification Using Substitution Variables	128
	5.7.3	Defining File Alias Using Extendable Lookup	130
	5.7.4	Support for Oracle Cloud Storage Access	130
	5.7.5	Consolidated Logging	131
	5.7.6	Diagnostics Support (WLDF)	131
	5.7.7	Global Cache Flush Support	133
	5.7.8	Java Flight Recorder Support	
	5.7.9	Work Manager Support	134
	5.7.10	Trust Store Support	135
Misc	ellaneou	us Operations and Configuration	136
6.1	Enablin	ng Email Logging from Log4j2	136
6.2		ling the Default Oracle Database Connection Information	
6.3	Central	lized Properties Customization	139
6.4	Cache I	Management	140

6.

		6.4.1 Server Cache	140
		6.4.2 Client Cache	142
		6.4.3 Oracle WebLogic: Expanded or Archive Format	142
	6.5	Implementing Custom Templates	143
		6.5.1 Additional Templates	144
	6.6	Sending Emails at the Conclusion of Batch Processes	146
	6.7	Oracle WebLogic Configuration Support	148
	6.8	Using Configuration Files Outside the WAR/EAR File	148
	6.9	Oracle RAC Support	150
	6.10	Adding a Custom Privacy Policy Screen	15:
	6.11	User Exit Include Files	151
		6.11.1 Properties File User Exits	154
	6.12	Custom JMS Configuration	155
	6.13	Online Transaction Timeouts	157
	6.14	Setting the Date for Testing Purposes	158
	6.15	Secure Transactions	160
	6.16	Native Oracle WebLogic Support	160
		6.16.1 Manual Re-Deployment Process	162
	6.17	Oracle WebLogic Console Operations	162
		6.17.1 Starting and Stopping from Console	163
		6.17.2 Monitoring Web Applications Using the Console	164
	6.18	Specifying Custom Log File Names	164
	6.19	Turning Off L2 Cache	165
	6.20	JDBC Support	166
	6.21	Cancelling Batch Processes Using JMX	167
7.	Oper	rations from Oracle Enterprise Manager	169
	7.1	Discovering Oracle Utilities Targets	169
	7.2	Discovering Oracle WebLogic Targets	170
	7.3	Oracle Utilities Targets	
	7.4	Monitoring Using Oracle Enterprise Manager	
8.	Orac	le Scheduler Integration	
	8.1	Introduction	
	8.2	Background Materials	
	8.3	Oracle Scheduler Interface Overview	
		8.3.1 Oracle Scheduler Configuration	
		8.3.2 Oracle Scheduler Execution	
	8.4	Oracle Scheduler Interface (OUAF_BATCH)	
		8.4.1 Submit Job - Submit a Job or Thread	
		8.4.2 Restart Thread - Restart a Failed Thread/Job	
		8.4.3 Cancel_Job - Cancel a Running Job	
		8.4.4 Set_Option - Set a Global or Job Option	
		8.4.5 Unset_Option - Reset a Global or Job Option	
		8.4.6 Raise_Thread_Error - Raise an Error	182
	8.5	Building a Schedule	182
		8.5.1 Recommended Tools	184

		8.5.2	Defining Programs	185
		8.5.3	Defining Job Classes	186
		8.5.4	Defining Schedules	187
		8.5.5	Defining Remote Destinations and Credentials	188
		8.5.6	Defining Jobs	190
		8.5.7	Defining Chains	191
		8.5.8	Other Scheduler Objects	192
		8.5.9	Setting Preferences	192
		8.5.10	Order of Preference	193
		8.5.11	Using soft_parm_map	193
		8.5.12	Using soft_parm_list	194
	8.6	Oracle 9	Scheduler – REST APIs	195
	8.7	Executi	ng Jobs	201
	8.8	Monito	ring Oracle Scheduler	202
		8.8.1	Job States	202
		8.8.2	Dictionary Views	202
		8.8.3	Scheduler Notifications	202
	8.9	Cancella	ation	202
	8.10	Exporti	ng Schedules Across Environments	203
Арр	endix .	A: P	arameters	204
	A.1		tions Used in This Section	204
	A.2	ENVIRO	N.INI	204
		A.2.1	ALLOW_SELFSIGNED_SSL – Enable Self Signed SSL	
		A.2.2	ANT_ADDITIONAL_OPT - Additional Options for ANT	
		A.2.3	ANT_HOME - Location of ANT	205
		A.2.4	ANT_OPT_MAX - ANT Maximum Heap Size	205
		A.2.5	ANT_OPT_MIN - ANT Minimum Heap Size	206
		A.2.6	BATCHDAEMON - Whether Online Batch Daemon is Enabled	206
		A.2.7	BATCHEDIT_ENABLED - Whether Batch Edit Facility is Enabled	206
		A.2.8	BATCHENABLED - Whether Online Batch Server is Enabled	207
		A.2.9	BATCHTHREADS - Number of Online Batch Server Threads	207
		A.2.10	BATCH_DBPASS - Batch User Password	207
		A.2.11	BATCH_DBUSER - Batch User	207
		A.2.12	BATCH_MEMORY_ADDITIONAL_OPT - Threadpool Worker JVM Additional Options	208
		A.2.13	BATCH_MEMORY_OPT_MAX - Threadpool Worker Java Maximum Heap Size	208
		A.2.14	BATCH_MEMORY_OPT_MIN - Threadpool Worker Java Minimum Heap Size	208
		A.2.15	BATCH_MODE - Default Mode of Batch	209
		A.2.16	BATCH_ONLINE_LOG_DIR - Online Batch Submission Log Directory	209
		A.2.17	BATCH_RMI_PORT - RMI Port for Batch	209
		A.2.18	BSN_APP - Business Server Application Name	209
		A.2.19	BSN_JMX_RMI_PORT_PERFORMANCE - JMX Port for Business Application Server	210
		A.2.20	BSN_JMX_SYSPASS - Password for BAS JMX Monitoring	210
		A.2.21	BSN_JMX_SYSUSER - Default User for BSN JMX Monitoring	210
		A.2.22	BSN_NODENAME - IBM WebSphere Node Name	211
		A.2.23	BSN_SVRNAME - IBM WebSphere Server Name	211
		A.2.24	BSN_WASBOOTSTRAPPORT - Bootstrap Port	211

A.2.25	BSN_WLHOST - Bootstrap Host	212
A.2.26	BSN_WLHOST - Business App Server Host	212
A.2.27	CALC_WLS_COMMON_JAR_DIR – Weblogic's Jersey Jars Directory	212
A.2.28	CALC_WLS_SERVER_JAR_DIR – Weblogic Server Lib Jars Directory	213
A.2.29	CHAR_BASED_DB – Specifies If the DB Is Char-Based	213
A.2.30	CLOUD_CUSTOM_WHITE_LIST_PATH - Custom URL Allow Lists for Cloud	213
A.2.31	CLOUD_LOCATION_F1_BASE_IWS_URI – URI for Variable F1_BASE_IWS_URI	214
A.2.32	CLOUD_LOCATION_F1_BASE_REST_URL - URI for Variable F1_BASE_REST_URL	214
A.2.33	CLOUD_LOCATION_F1_BASE_WEB_URI - URI for Variable F1_BASE_WEB_URI	214
A.2.34	CLOUD_LOCATION_F1_MIGR_ASSISTANT_FILES – Location of CMA Files for Migrations	215
A.2.35	CLOUD_LOCATION_F1_OAUTH2_URI – URI for OAUTH2	215
A.2.36	CLOUD_LOCATION_F1_OPEN_API_BASE_URL - URI for variable F1_OPEN_API_BASE_URL	215
A.2.37	CLOUD_RESTRICTIONS_URLS_ENABLE - Enable or Disable URL Restrictions	216
A.2.38	CLOUD_SUBSTITUTION_VARIABLE_LIST_FILE_LOCATION - Enable or Disable URL Restrictions	216
A.2.39	CLOUD_WHITE_LIST_PATH - URL Allow Lists for Cloud	216
A.2.40	CMPDB - Database Type	217
A.2.41	CM_INSTALL_SAMPLE - Whether samples are installed	217
A.2.42	COHERENCE_CLUSTER_ADDRESS - Multicast address for Batch Cluster	217
A.2.43	COHERENCE_CLUSTER_MODE - Batch Cluster Mode	218
A.2.44	COHERENCE_CLUSTER_NAME - Batch Cluster Name	218
A.2.45	COHERENCE_CLUSTER_PORT - Batch Cluster Port Number	219
A.2.46	CONSOLIDATED_LOG_FILE_PATH – Directory for Consolidated Log File	219
A.2.47	CSP_CONNECT_SRC - Custom URI for Content Security Policy connect-src	219
A.2.48	CSP_FONT_SRC - Custom URI for Content Security Policy font-src	220
A.2.49	CSP_STYLE_SRC - Custom URI for Content Security Policy style-src	220
A.2.50	CSP_URL_IMG_SRC - Custom URI for Content Security Policy img-src	220
A.2.51	CSP_URL_SCRIPT_SRC - Custom URI for Content Security Policy script-src	220
A.2.52	CORS_ALLOWED_FRAME_ANCESTORS_MAX_NUMBER - Maximum Number of Frame Ancestors	221
A.2.53	CORS_ALM_DOMAIN - URI for Variable ALM_DOMAIN	221
A.2.54	CORS_CSP_FRAME_ANCESTOR_HOST1 - URI for Substitution Variable CSP_FRAME_ANS_HOST1	221
A.2.55	CORS_CSP_FRAME_ANCESTOR_HOST2 - URI for Substitution Variable CSP_FRAME_ANS_HOST2	222
A.2.56	CORS_FA_DOMAIN - URI for variable FA_DOMAIN	222
A.2.57	CORS_HOST – Source for Cross Origin Resource Sharing	222
A.2.58	CORS_SCHEME – Scheme to be used for Cross Origin Resource Sharing	223
A.2.59	CSRF_PROTECTION – Cross-Site Request Forgery Protection	223
A.2.60	CUSTOM_SQL_SECURITY – Enable Custom SQL Security	223
A.2.61	DBCONNECTION - JDBC Connection String	224
A.2.62	DBDRIVER - Database Driver	224
A.2.63	DBNAME - Database Name	224
A.2.64	DBPASS - Online Database User Password	225
A.2.65	DBPASS_GEOCODE_WLS - GEOCODE Database Password	225
A.2.66	DBPASS_MDS - MDS Database Password	225
A.2.67	DBPASS_ORASDPM - DPM Database Password	226
A.2.68	DBPASS_OSB - OSB Database Password	226
A.2.69	DBPASS_SOAINFRA - SOA Database Password	227
A.2.70	DBPORT - Database Listener Port	227

A.2.71	DBSERVER - Database Server	227
A.2.72	DBURL_GEOCODE - GEOCODE JDBC URL	228
A.2.73	DBURL_OSB - OSB JDBC URL	228
A.2.74	DBURL_SOA - SOA Suite JDBC URL	228
A.2.75	DBUSER - Online Database User	228
A.2.76	DBUSER_GEOCODE - GEOCODE Database User	229
A.2.77	DBUSER_MDS - SOA MDS Database User	229
A.2.78	DBUSER_ORASDPM - DPM Database User	229
A.2.79	DBUSER_OSB - OSB Database User	230
A.2.80	DBUSER_SOAINFRA - SOA Database User	230
A.2.81	DB_OVERRIDE_CONNECTION - Custom JDBC URL	230
A.2.82	DESC - Environment Description	231
A.2.83	DIALECT - Hibernate Dialect	231
A.2.84	DIRSEP - Directory Separator	231
A.2.85	DOC1BILLSCRIPT - Name of External Print Script	232
A.2.86	DOC1SCRIPT - Name of Generic Print Script	232
A.2.87	ENABLE_CORS – Enable Cross Origin Resource Sharing	232
A.2.88	ENABLE_JMS_GLOBAL_FLUSH – Enable Flushing of JMS	233
A.2.89	ENCODING - Whether Encryption Is Enabled	233
A.2.90	ENVIRONMENT_ID - Environment Identifier	233
A.2.91	FORCE_HTTP – Enforce HTTP Protocol	234
A.2.92	FW_VERSION - Oracle Utilities Application Framework Version	234
A.2.93	FW_VERSION_NUM - Oracle Utilities Application Framework Version Identifier	234
A.2.94	GIS - GIS Support	235
A.2.95	GIS_URL - GIS Service URL	235
A.2.96	GIS_WLSYSPASS - GIS WebLogic System Password	235
A.2.97	GIS_WLSYSUSER - GIS WebLogic System User Id	236
A.2.98	GLOBAL_JVMARGS - Additional JVM Arguments	236
A.2.99	HEADEND_CD_CB - Headend System URI for SOA Configuration Plan (CD_CB)	236
A.2.100	HEADEND_MR_CB - Headend System URI for SOA Configuration Plan (MR_CB)	237
A.2.101	HIBERNATE_JAR_DIR - Location of Hibernate JAR Files	237
A.2.102	HIGHVALUE - Language Specific Highvalues	237
A.2.103	HSTS_MAX_AGE – Maximum Age of Strict Transport Security	238
A.2.104	HSTS_PRELOAD – Strict Transport Security Preload	238
A.2.105	HSTS_SUBDOMAINS – Subdomains Included in Strict Transport Security	238
A.2.106	IWS_JDBC_NAME - JNDI Name for the IWS Connection Pools	239
A.2.107	IWSWAR - Name of Inbound Web Services WAR	239
A.2.108	JAVAENCODING - Java Language Encoding	239
A.2.109	JAVA_HOME - Location of Java SDK	240
A.2.110	JAVA_VENDOR - Java Vendor	240
A.2.111	JAVA_VERSION - JVM Version String	240
A.2.112	JAVA_VERSION_MAIN - Abbreviated JVM Version	240
A.2.113	JDBC_NAME - JNDI Name for the Online JDBC Data Source	241
A.2.114	JDBC_TIMEOUT - JDBC Read Timeout	241
A.2.115	JNDI_GEOCODE - Geocode Data Source JNDI	241
A.2.116	JMX_HTTPSSL_FLAG - SSL flag for JMX	242

A.2.11/	JMX_HTTPSSL_KEYPAIR_PASSPHRASE - Keypair Passphrase forRESTJMX	242
A.2.118	JMX_HTTPSSL_KEYSTORE_FILE - Keystore file path for REST JMX	242
A.2.119	JMX_HTTPSSL_KEYSTORE_TYPE - Keystore type for REST JMX	242
A.2.120	JMX_HTTPSSL_KEYSTORE_PASSPHRASE - Keystore Passphrase for REST JMX	243
A.2.121	JMX_HTTPSSL_TRUSTSTORE_FILE - Truststore file path for REST JMX	243
A.2.122	JMX_HTTPSSL_TRUSTSTORE_PASSPHRASE - Truststore Passphrase for REST JMX	243
A.2.123	JMX_HTTPSSL_TRUSTSTORE_TYPE - Truststore Type for REST JMX	244
A.2.124	JMX_REST_CONTEXT - JMX REST Server Context	244
A.2.125	JMX_REST_PORT_BATCH - Batch Server JMX Port Number for REST Server	244
A.2.126	JMX_REST_PORT_SERVICE - Business Server JMX Port Number for REST Server	244
A.2.127	JMX_REST_PORT_WEB - Web Server JMX Port Number for REST Server	245
A.2.128	JMX_REST_SERVICE_FLAG - Enable/Disable REST Service for JMX	245
A.2.129	JMX_REST_SERVICE_HOST - Hostname to Run the REST Server	245
A.2.130	JNDI_OSB - OSB Data Source JNDI	246
A.2.131	KS_IMPORT_KEYSTORE_FOLDER – Keystore Import Folder	246
A.2.132	LD_LIBRARY_PATH - Library Path for Windows/Linux/Solaris	246
A.2.133	MODULES - Names of Modules Installed (Deprecated)	247
A.2.134	MALWARE_SCAN_HOST	247
A.2.135	MALWARE_SCAN_PORT	247
A.2.136	MALWARE_SCAN_TIMEOUT	248
A.2.137	NLS_LANG - NLS Language Setting	248
	ONLINE_DISPLAY_HOME - Location of Print Rendering Software	
A.2.139	ONS_JAR_DIR - Location of Oracle Notification Service Libraries	249
	ONSCONFIG - ONS Configuration	
A.2.141	OPSYS - Operating System	249
A.2.142	ORACLE_CLIENT_HOME - Oracle Client Home	250
A.2.143	ORACLE_GUIDED_LEARNING_ID - Oracle Guided Learning ID	250
A.2.144	OSB_HOME - Oracle Service Bus Home	250
A.2.145	OSB_HOST - Oracle Service Bus Host Name	251
A.2.146	OSB_LOG_DIR - Default Location For Oracle Service Bus Logs	251
A.2.147	OSB_PASS_WLS - Password for Oracle Service Bus User	251
A.2.148	OSB_PORT_NUMBER - Oracle Service Bus Port Number	252
A.2.149	OSB_USER - User Name for Oracle Service Bus	252
A.2.150	OUAF_DBMS_SCHEDULER_USER – DB User of DBMS Scheduler	252
A.2.151	OWSM_PROTECTION_FOR_REST_SERVICES – Enable Oracle Web Services Manager Protection for RE. 253	ST
A.2.152	PERLHOME - Location of PERL	253
A.2.153	SERVER_ROLES - Which Server Roles Are Enabled	253
A.2.154	SERVER_ROLE_BATCH - Whether the Batch Server Is Enabled In This Installation	254
A.2.155	SERVER_ROLE_INTEGRATION - Whether the IWS Server Is Enabled In This Installation	254
A.2.156	SERVER_ROLE_ONLINE - Whether the Online Server Is Enabled In This Installation	254
A.2.157	SOA_HOME - Location of Oracle SOA Suite	255
A.2.158	SOA_HOST - Hostname for Oracle SOA Suite	255
A.2.159	SOA_PORT_NUMBER - Port Number for Oracle SOA Suite	255
A.2.160	SPLADMIN - Administration Userid	256
A.2.161	SPI ADMINGROUP - Administration Group	256

A.2.162	SPLApp - Name of Unline WAR File	256
A.2.163	SPLDIR - Home Directory of Product	256
A.2.164	SPLDIROUT - Location of Product Output	257
A.2.165	SPLENVIRON - Environment Identifier	257
A.2.166	SPLOUTPUT - Directory for Product Output	257
A.2.167	SPLSERVICEAPP - Name of Business Application Server Application	258
A.2.168	SPLWEBAPP – Name of Web Application Server Application	258
A.2.169	STRICT_TRANSPORT_SECURITY – Enable Strict Transport Security	258
A.2.170	STRIP_HTML_COMMENTS - Strip Out Comments In Code	259
A.2.171	TEMPSTORAGE_SPLITFILESIZE - Split File Size in MB	259
A.2.172	TOP_VERSION - Product Version	259
A.2.173	TOP_VERSION_NUM - High Level Product Version	260
A.2.174	TMP_FILE_LOCATION - Temporary File Location	260
A.2.175	WEB_ADMIN_SERVER – Name of the Web Admin Server	260
A.2.176	WEB_APP – Name of WebSphere Server Application	260
A.2.177	WEB_APPVIEWER_FORM_LOGIN_ERROR_PAGE – App Viewer Form Login Error Page	261
A.2.178	WEB_APPVIEWER_FORM_LOGIN_PAGE – App Viewer Form Login Page	261
A.2.179	WEB_APPVIEWER_PRINCIPAL_NAME - Application Viewer Principal Name	261
A.2.180	WEB_APPVIEWER_ROLE_NAME - Application Viewer Security Role	261
A.2.181	WEB_CONTEXT_ROOT - Web Context Root	262
A.2.182	WEB_DEPLOY_JAVADOCS - Deploy JavaDocs	262
A.2.183	WEB_DEPLOY_APPVIEWER – Deploy AppViewer	262
A.2.184	WEB_DEPLOY_EAR - Deploy EAR File	263
A.2.185	WEB_ENABLE_HEALTHCHECK - Enable System Healthcheck	263
A.2.186	WEB_FORM_LOGIN_ERROR_PAGE - Default Form Login Error Page	263
A.2.187	WEB_FORM_LOGIN_PAGE - Default Form Login Page	264
A.2.188	WEB_HELP_FORM_LOGIN_ERROR_PAGE - Help Form Login Error Page	264
A.2.189	WEB_HELP_FORM_LOGIN_PAGE - Help Form Login Page	264
A.2.190	WEB_ISDEVELOPMENT - Development Environment	265
A.2.191	WEB_ISJAVADOCS - Install application JAVADOCS	265
A.2.192	WEB_IWS_MDB_RUNAS_USER - Default User for MDB to Run as within Product	265
A.2.193	WEB_IWS_SUPER_USERS - Users to Run as in IWS	266
A.2.194	WEB_JAVADOCS_FORM_LOGIN_ERROR_PAGE - Javadocs Login Error Page	266
A.2.195	WEB_JAVADOCS_FORM_LOGIN_PAGE - Javadocs Login Page	266
A.2.196	WEB_JAVADOCS_PRINCIPAL_NAME - Javadocs Principal Name	267
A.2.197	WEB_JAVADOCS_ROLE_NAME - Javadocs Security Role Name	267
A.2.198	WEB_JMX_RMI_PORT_PERFORMANCE - JMX Port for Web Application Server Monitoring	267
A.2.199	WEB_L2_CACHE_MODE - Turn Off L2 Cache for Online Submission	268
A.2.200	WEB_MAXAGE - Text Cache	268
A.2.201	WEB_MAXAGEI - Image Cache	268
A.2.202	WEB_NODENAME - IBM WebSphere ND Node Name	269
A.2.203	WEB_PRELOADALL - Preload All Pages on Startup	269
A.2.204	WEB_PRINCIPAL_NAME - Default JEE Authorization Principal	269
A.2.205	WEB_ROLE_NAME - Default JEE Authorization Role	270
A.2.206	WEB_SERVER_HOME - Location of Web Application Server	270
A.2.207	WEB_SERVER_VERSION - Web Server Version	270

	A.2.208	WEB_SERVER_VERSION_MAIN	. 2/1
	A.2.209	WEB_SERVER_VERSION_PATCH_FLAG	. 271
	A.2.210	WEB_SVRNAME - IBM WebSphere Server Name	. 271
	A.2.211	WEB_WASPASS - IBM WebSphere JNDI Password	. 272
	A.2.212	WEB_WASUSER - IBM WebSphere JNDI UserID	. 272
	A.2.213	WEB_WLAUTHMETHOD - Authentication Method	. 272
	A.2.214	WEB_WLHOST - Web Server Host	. 273
	A.2.215	WEB_WLPAGECHECKSECONDS - Interval for Recompilation of JSP	. 273
	A.2.216	WEB_WLPORT - Web Server HTTP Port	. 273
	A.2.217	WEB_WLSSLPORT - Oracle WebLogic SSL HTTP Port	. 274
	A.2.218	WEB_WLSYSPASS - Oracle WebLogic JNDI System Password	. 274
	A.2.219	WEB_WLSYSUSER - Oracle WebLogic JNDI System Userid	. 274
	A.2.220	WEB_WLS_SVRNAME - Oracle WebLogic Server Name	. 275
	A.2.221	WLS_ADMIN_PORT - Admin Console Port Number	. 275
	A.2.222	WLS_CLUSTER_NAME - Name of Cluster for Product	. 275
	A.2.223	WLS_DIAGNOSTIC_CONTEXT_ENABLED - ECID Support	. 276
	A.2.224	WLS_DOMAIN_HOME - Oracle WebLogic Domain Home	. 276
	A.2.225	WLTHINT3CLIENT_JAR_DIR - Location of Thin WebLogic T3 Client	. 276
	A.2.226	WL_HOME - Oracle WebLogic Home	. 277
	A.2.227	XAI_DBPASS - Password for Database User for IWS	. 277
	A.2.228	XAI_DBUSER - Database User for IWS	. 277
	A.2.229	XQUERIES_TO_CACHE - Size of XQuery Cache	. 278
	A.2.230	XQUERY_CACHE_FLUSH_TIMEOUT - Cache Life for XQueries	. 278
A.3	Web.xm	l	.279
	A.3.1	Filter Mappings - JEE Filters	. 279
	A.3.2	disableCompression - Disable Compression	. 280
	A.3.3	maxAgel - Max Age for Images	. 281
	A.3.4	maxAge - Max Age for Pages	. 282
	A.3.5	auth-method - Authorization Method	. 283
	A.3.6	fieldValuesAge - Server Cache Lifetime	. 284
	A.3.7	disableUIPageCompression - Disable UI Compression	. 285
A.4	spl.prop	erties	.286
	A.4.1	calendar.japanese.eras - Japanese Era Definition	. 286
	A.4.2	com.oracle.ouaf.customer.whitelist.file – Customer's URL Allow List File	. 287
	A.4.3	com.oracle.ouaf.consolidatedLog.fileName – Consolidate Log File	. 287
	A.4.4	com.oracle.ouaf.dbms.scheduler.schema – DBMS Scheduler Object's Schema	. 288
	A.4.5	com.oracle.ouaf.file.tempstorage.dir – Location for Temporary File	. 288
	A.4.6	com.oracle.ouaf.file.tempstorage.splitfilesize – Split File Size in MB	. 289
	A.4.7	com.oracle.ouaf.groovy.precompile.allscripts - Enable Precompilation of Groovy Scripts	. 289
	A.4.8	com.oracle.ouaf.groovy.precompile.maxWaitTime - Max Wait Timefor Groovy Scripts Precompilation	. 290
	A.4.9	com.oracle.ouaf.migrationAssistant.exportDirectory – Directory for Exported CMA File	. 290
	A.4.10	com.oracle.ouaf.migrationAssistant.importDirectory – Directory for CMA File for Import	. 291
	A.4.11	com.oracle.ouaf.migrationAssistant.fileExtension – Extension of CMA File	. 291
	A.4.12	com.oracle.ouaf.proxy.password – Proxy Credentials for Senders if JVM is Configured to Use Proxy	. 292
	A.4.13	com.oracle.ouaf.proxy.user – Proxy Credentials for Senders if JVM is Configured to Use Proxy	. 292
	A.4.14	com.oracle.ouaf.system.database.disableTagging - Disables Database Tagging	. 293

A.4.15	com.oracle.ouaf.ui.disableRequiredFieldIndicators – Disable Required Field Indicators on UI Map	293
A.4.16	com.oracle.ouaf.uriSubstitutionVariables.file – URI Predefined Variables List File	294
A.4.17	com.oracle.ouaf.uriValidation.enable – Enable Restriction of URLs	294
A.4.18	com.oracle.ouaf.web.allowCORS - Enable Cross Origin Resource Sharing	295
A.4.19	com.oracle.ouaf.web.csp.enable - Enable Content Security Policy	295
A.4.20	com.oracle.ouaf.web.cspReporting.enable - Enable Content Security Policy reporting	296
A.4.21	com.oracle.ouaf.web.csp.allowedFrameAnsMaxNumber - Allowed Frame Ancestors Max Number	296
A.4.22	com.oracle.ouaf.web.disableScreenHideSessionTimeout- Disables Screen Hide on Session Timeout	297
A.4.23	com.oracle.ouaf.web.disableSecureCookie - Web Pages User Experience Style	297
A.4.24	com.oracle.ouaf.web.userInterfaceStyle - Web Pages User Experience Style	298
A.4.25	com.oracle.ouaf.web.oracleGuidedeLearningId - Oracle Guided Learning Identifier	298
A.4.26	com.oracle.ouaf.whitelist.file – Oracle URL Allow List Filename and Location	299
A.4.27	com.oracle.XPath.LRUSize - XPath Cache	299
A.4.28	com.oracle.XPath.flushTimeout - XPath Flush	299
A.4.29	com.splwg.batch.cluster.jvmName - Online Batch JVM Name	300
A.4.30	com.splwg.batch.scheduler.daemon - Online Submission Daemon	300
A.4.31	com.splwg.grid.executionMode - Online Execution Mode	
A.4.32	com.splwg.grid.online.enabled - Online Batch Server	
A.4.33	com.splwg.grid.distThreadPool.threads.DEFAULT - Online Submission Threadpool	
A.4.34	com.splwg.schema.newValidations.F1 - Set Behavior of Validations	
A.4.35	jmx.remote.x.access.file - JMX Access Control	
A.4.36	jmx.remote.x.password.file - JMX Password Control	
A.4.37	oracle.ouaf.jmx.httpssl.flag - SSL Flag for JMX REST	
A.4.38	oracle.ouaf.jmx.httpssl.keypair.passphrase - Keypair Passphrase for REST JMX	
A.4.39	oracle.ouaf.jmx.httpssl.keystore.file.path - Keystore File Path for REST JMX	
A.4.40	oracle.ouaf.jmx.httpssl.keystore.passphrase - Keystore Passphrase for REST JMX	
A.4.41	oracle.ouaf.jmx.httpssl.keystore.type - Keystore Type for REST JMX	
A.4.42	oracle.ouaf.jmx.httpssl.truststore.filepath - Truststore File Path for REST JMX	
A.4.43	oracle.ouaf.jmx.httpssl.truststore.passphrase - Truststore Passphrase for REST JMX	
A.4.44	oracle.ouaf.jmx.httpssl.truststore.type - Truststore type for REST JMX	
A.4.45	jmx.remote.x.password.file - JMX Password Control	
A.4.46	oracle.ouaf.jmx.remote.startPort - JMX Override Port	
A.4.47	oracle.ouaf.jmx.rest.context - JMX REST Context	
A.4.48	oracle.ouaf.jmx.rest.port.batch - Batch Server JMX Port Number for REST Server	
A.4.49	oracle.ouaf.jmx.rest.port.service - Business Server JMX Port Number for REST Server	
A.4.50	oracle.ouaf.jmx.rest.port.web - Web Server JMX Port Number for REST Server	
A.4.51	oracle.ouaf.jmx.rest.service.flag - Enable/Disable REST Service for JMX	
A.4.52	oracle.ouaf.jmx.rest.service.host - Hostname to Run the JMX REST Server	
A.4.53	oracle.ouaf.malware.scan.host - Host URI for Attachment Malware Scanning	
A.4.54	oracle.ouaf.malware.scan.timeout - Timeout for Attachment Malware Scanning	
A.4.55	ouaf.accessiblity.features - Enable Accessibility Features	
A.4.56	ouaf.attachment.disableSpecialCharCheckOnFileName - Disable Special Characters on File Name	
A.4.57	ouaf.batch.onlineLogDir - Online Line Batch Log Directory	
A.4.58	ouaf.batch.onlineLogDir.retain – Retain Online Line Batch Log Files	
A.4.59	ouaf.database.session.setInstallationTimeZone - Set Time Zone for Sessions	
A.4.60	ouaf.flush.jms.disabled - Global Flush Supported	

A.4.61	ouaf.flush.jms.connection - Connection Factory for Global Flush	314
A.4.62	ouaf.flush.jms.requestTopic - Global Flush Request Topic	314
A.4.63	ouaf.flush.jms.responseTopic - Global Flush Response Topic	315
A.4.64	ouaf.runtime.compatibility.enablePrecisionScaleOnMoney - Money Processing	315
A.4.65	ouaf.jmx.com.oracle.ouaf.ws.mbeans.WSFlushBean - WS Cache Flush	316
A.4.66	ouaf.jmx.com.splwg.base.support.management.mbean.JVMInfo - JVM Information	316
A.4.67	ouaf.jmx.com.splwg.base.web.mbeans.FlushBean - Manage Cache	317
A.4.68	ouaf.list.buffer.limit - List Iteration Limit	317
A.4.69	ouaf.messaging.transformerfactory - Transformer	318
A.4.70	ouaf.shortcut.ignore.altKeys - Disable Hot Keys	318
A.4.71	ouaf.timeout.business_object.default - Set Default Business Object Timeout	319
A.4.72	ouaf.timeout.business_object. bocode> - Set Specific Business Object Timeout	319
A.4.73	ouaf.timeout.business_service.default - Set Default Business Service Timeout	320
A.4.74	ouaf.timeout.business_service. bscode> - Set Specific Business Service Timeout	320
A.4.75	ouaf.timeout.query.default - Set Default Query Timeout	321
A.4.76	ouaf.timeout.query. <zonecode> - Set Specific Query Timeout</zonecode>	322
A.4.77	ouaf.timeout.script.default - Set Default Script Timeout	323
A.4.78	ouaf.timeout.script. <scriptname> - Set Specific Script Timeout</scriptname>	324
A.4.79	ouaf.timeout.service.default - Set Default Service Timeout	325
A.4.80	ouaf.timeout.service. <service> - Set Specific Service Timeout</service>	325
A.4.81	ouaf.web.appViewer.coreAppURL - AppViewer Callback URL	326
A.4.82	ouaf.web.disablePreload - Disable Screen Preload	326
A.4.83	ouaf.web.help.coreAppURL - Help Callback URL	327
A.4.84	ouaf.web.helpRootURL - Help URL	327
A.4.85	ouaf.web.JspHeader.maxAge - JSP Age	328
A.4.86	ouaf.web.preloadAllPages - Preload Scope	328
A.4.87	ouaf.web.useOHW - Use Oracle Help for Web Engine	329
A.4.88	ouaf.weblogic.enableDiagnostics - Enable ECID Tracking	329
A.4.89	ouaf.webservices.security.defaultPolicy – IWS Customized Security Policy	330
A.4.90	ouaf.ws.defaultUser - Default User for Web Services	330
A.4.91	ouaf.ws.deploy.appxml.file - Application XML File for Inbound Web Services	331
A.4.92	ouaf.ws.deploy.ear - EAR File Name for Inbound Web Services	331
A.4.93	ouaf.ws.deploy.contextpath - Context Path for Inbound Web Services	332
A.4.94	ouaf.ws.pageService.annotations - Security Annotation for XAI Legacy services	332
A.4.95	ouaf.ws.superusers - Effective Web Services Users	333
A.4.96	ouaf.ws.tools.artifact.generated.buildfile - Build File	333
A.4.97	ouaf.ws.tools.artifact.generated.sourcedir - Location of generated source	334
A.4.98	ouaf.ws.tools.artifact.resource.dir - Location of Resources	334
A.4.99	ouaf.ws.tools.artifact.schema.dir - Location of Schemas	335
A.4.100	ouaf.ws.tools.artifact.xsl.dir - Web Service XSL Location	335
A.4.101	ouaf.ws.tracing - Inbound Web Services Tracing	336
A.4.102	ouaf.ws.xslDirOverride - Override XSL Location	336
A.4.103	spl.csv.delimiter.useFromDisplayProfile - List CSV Delimiter	337
A.4.104	spl.ejbContainer.contextFactory - Context Factory for Business Application Server	337
A.4.105	spl.ejbContainer.password - Password for Business Application Server	338
A.4.106	spl.eibContainer.url - Business Application Server URI	338

A.4.107	spl.ejbContainer.user - Business Application Server User	339
A.4.108	spl.geocodeDatasource.contextFactory - GIS Context Factory	339
A.4.109	spl.geocodeDatasource.password - GIS Connection Password	340
A.4.110	spl.geocodeDatasource.url - GIS Data Source	340
A.4.111	spl.geocodeDatasource.user - GIS Connection User	340
A.4.112	spl.runtime.compatibility.uiMapDisableInputValue - Map Defaults	341
A.4.113	spl.runtime.compatibility.uiMapDropdownSelectFirstValue – Drop-down defaults	341
A.4.114	spl.runtime.compatibility.uiMapDisableTitle - Screen Title Defaults	342
A.4.115	spl.runtime.compatibility.uiMapDisableGenerateUniqueHtmlIDs - Map IDs	343
A.4.116	spl.runtime.customSQLSecurity – Enable SQL Allow List	343
A.4.117	spl.runtime.disableCSRFProtection - Disable Security Tokens	344
A.4.118	spl.runtime.environ.init.dir - Location of Configuration Files	344
A.4.119	spl.runtime.environ.isWebExpanded - Expanded Mode	345
A.4.120	spl.runtime.environ.SPLEBASE - Location of Software	345
A.4.121	spl.runtime.initiatize.waittime - Start Time Delay	346
	spl.runtime.environ.SPLOUTPUT - Location of Output	
	spl.runtime.management.batch.cluster.url - Batch Cluster URL	
	spl.runtime.management.connector.url.default - JMX URL	
	spl.runtime.management.rmi.port - JMX Port	
	spl.runtime.options.isFCFEnabled - RAC FCF Enabled	
	spl.runtime.options.onsserver=nodes - ONS Configuration	
	spl.runtime.options.allowSystemDateOverride - Set Testing Date	
	spl.runtime.options.createSimpleWebAppContextEnable - Web Cache Loading	
	spl.runtime.options.isDevelopmentMode - Development Mode	
	spl.runtime.oracle.statementCacheSize - Java SQL Cache Size	
	spl.runtime.performSignedNumberValidation. <pre>rvalidation</pre>	
	spl.runtime.service.extraInstallationServices - Installation Service	
	spl.runtime.sql.highValue - SQL High Value	
	spl.runtime.utf8Database - UTF8 Support	
	spl.runtime.warning.dialog.before.download - Enable Warning Message Before Data Download	
	spl.serviceBean.jndi.name - JNDI Name for Business Application Server	
	spl.tools.loaded.applications - Loaded Product	
	ouaf.propertyfile.usage – Properties Usage	
	e.properties	
A.5.1	hibernate.cache.use_second_level_cache - Use Cache	
A.5.2	hibernate.connection.datasource - JNDI Data Source	
A.5.3	hibernate.connection.driver_class - Connection Driver Class	
A.5.4	hibernate.connection.password - Database User Password	
	hibernate.connection.provider_class - Connection Provider	
A.5.5		
A.5.6	hibernate.connection.release_mode - Connection Release	
A.5.7	hibernate.connection.url - JDBC URL	
A.5.8	hibernate.connection.username - Database User	
A.5.9	hibernate.dialect - Dialect Used	
A.5.10	hibernate.jdbc.batch_size - JDBC2 Update Support	
A.5.11	hibernate.jdbc.fetch_size - Solution Set Size	
A.5.12	hibernate.max_fetch_depth - Join Fetch Depth	362

A.5

	A.5.13	hibernate.query.factory_class - HQL Parser	. 363
	A.5.14	hibernate.query.substitutions - Literal Mappings	363
	A.5.15	hibernate.show_sql - Debug Mode	364
	A.5.16	hibernate.transaction.factory_class - Transaction Class	364
	A.5.17	hibernate.ucp.connection_wait_timeout - UCP Connection Timeout	365
	A.5.18	hibernate.ucp.inactive_connection_timeout - Connection Inactivity Timeout	365
	A.5.19	hibernate.ucp.jmx_enabled - Enable UCP JMX	366
	A.5.20	hibernate.ucp.max_size - Maximum Pool Size	366
	A.5.21	hibernate.ucp.max_statements - SQL Buffer Size	367
	A.5.22	hibernate.ucp.min_size - Minimum Pool Size	367
A.6	submitb	patch.properties (BATCH)	368
	A.6.1	coherence.management.remote - Enable/Disable Remote Management of Cluster Members	368
	A.6.2	com.ouaf.batch.jvmoptions - JVM Options	369
	A.6.3	com.splwg.grid.executionMode - Mode of Execution	369
	A.6.4	com.splwg.batch.submitter - THIN Submitter	370
	A.6.5	com.splwg.batch.submitter.batchCd - Batch Code	370
	A.6.6	com.splwg.batch.submitter.distThreadPool - Threadpool	371
	A.6.7	com.splwg.batch.submitter.languageCd - Language Code	
	A.6.8	com.splwg.batch.submitter.maximumCommitRecords - Commit Interval	
	A.6.9	com.splwg.batch.submitter.promptForValues - Prompt for Values	
	A.6.10	com.splwg.batch.submitter.processDate - Business Date	373
	A.6.11	com.splwg.batch.submitter.rerunNumber - Re Run Number	
	A.6.12	com.splwg.batch.submitter.softParameter - Job Parameters	
	A.6.13	com.splwg.batch.submitter.threadCount - Thread Limit	374
	A.6.14	com.splwg.batch.submitter.threadNumber - Thread Number	
	A.6.15	com.splwg.batch.submitter.traceProgramEnd - Trace Program End	
	A.6.16	com.splwg.batch.submitter.traceProgramStart - Trace Program Start	376
	A.6.17	com.splwg.batch.submitter.traceSQL - Trace SQL Statements	376
	A.6.18	com.splwg.batch.submitter.traceStandardOut - Trace Output Statements	377
	A.6.19	com.splwg.batch.submitter.userId - Security User	377
	A.6.20	spl.runtime.batch.L2CacheMode - L2 Cache Control	
	A.6.21	tangosol.coherence.distributed.localstorage - Cache Mode	378
	A.6.22	tangosol.coherence.role - Submitter Role	
A.7		oolworker.properties (BATCH)	
	A.7.1	com.oracle.ouaf.batch.scriptDir - Base Scripts Directory for Infrastructure Job	
	A.7.2	com.ouaf.batch.disableAutoFlush – Auto Flush Batch L2 Cache	
	A.7.3	com.ouaf.batch.flushIntervalInSeconds – Batch L2 Cache Auto Flush Interval	
	A.7.4	com.ouaf.batch.jvmoptions - Threadpool JVM Options	
	A.7.5	com.splwg.grid.executionMode - Threadpool Mode of Execution	
	A.7.6	com.splwg.grid.distThreadPool.threads - Threadpool Thread Limit	
	A.7.7	com.splwg.batch.scheduler.daemon - Scheduler Daemon	
	A.7.8	jmx.remote.x.access.file – JMX Access Control	
	A.7.9	jmx.remote.x.password.file – JMX Password Control	
	A.7.10	oracle.ouaf.jmx.remote.maxPortsToTry - Ports to Attempt to Connect to	
	A.7.11	oracle.ouaf.jmx.remote.startPort - Override Batch JMX Port	
	A.7.12	ouaf.batch.onlineLogDir - Online Line Batch Log Directory	

	A.7.13	ouaf.batch.onlineLogDir.retain – Retain Online Line Batch Log Files	387
	A.7.14	spl.runtime.batch.disableDeferredKeyInserts - Deferred Key Inserts	387
	A.7.15	spl.runtime.batch.L2CacheMode - Threadpoolworker L2 Cache Control	388
	A.7.16	spl.runtime.management.connector.url.default - Batch JMX URL	389
	A.7.17	spl.runtime.management.rmi.port - Batch JMX Port	389
	A.7.18	spl.runtime.options.isDevelopmentMode – Development Mode	390
	A.7.19	tangosol.coherence.distributed.localstorage - DistributedCache Storage	391
	A.7.20	tangosol.coherence.distributed.threads - Internal Cache Threads	391
	A.7.21	tangosol.coherence.invocation.threads - Internal Invocation Threads	392
	A.7.22	tangosol.coherence.localhost - Unicast Host Address	392
	A.7.23	tangosol.coherence.localport - Unicast Port	393
	A.7.24	tangosol.coherence.localport.adjust - Unicast Port Adjustment	393
	A.7.25	tangosol.coherence.role - Threadpoolworker Role	394
A.8	coherer	nce-cache.config.xml	395
A.9	tangoso	ol-coherence-override.xml	395

1. Architecture

Oracle Utilities Application Framework applications are multi-layered products with distinct tiers. The figure below illustrates its architecture:




Figure 1: Product Architecture

The components of the architecture are as follows:

- **Browser Client** The client component is a browser-based interface, which is light and only requires the Internet Explorer browser to operate.
- **Web Services Client** The client component for integration is web service based with support for both SOAP and REST protocols.
- Communication between the client and server uses the HTTPS protocol across a TCP/IP network.
 Non communications (HTTP) are also supported. The user simply uses a URL containing the product hostname and allocated port number in the address bar of Internet Explorer to access the application.

Points to Note:

It is possible to use proxies to hide or translate the hostname and port numbers. Refer to the documentation provided with the Oracle WebLogic documentation for proxy support instructions.

By default, SSL is enabled with minimal facilities, by default for all new installations. Refer to the SSL documentation provided with Oracle WebLogic to enable SSL to your individual needs.

The default SSL certificate provided by Oracle is recommended for demonstration and development purposes only. It is highly recommended that customers purchase their own certificates for use for SSL.

- Web Application Server (WAS) The product web application is housed in a JEE compliant web application server (Refer to the Supported Platforms section of the Oracle Revenue Management and Billing Installation Guide for Oracle WebLogic versions supported). This server can be run on a variety of supported Linux and UNIX platforms (Refer to the Supported Platforms section of the Oracle Revenue Management and Billing Installation Guide for operating systems and versions supported). Within the web application server, the pages for the product are rendered using a combination of metadata and formatting rules to ensure a consistent look and feel. These pages are written using a combination of JEE Java script and Java. These pages are cached on the web server and served to the client upon request. If the page requires business rules to be invoked, then business objects are called from this server.
- Business Application Server (BAS) The business component of the architecture can be installed as part of the web application server (default) or as a separate component. This means the business application server is also housed in a JEE compliant web application server (Refer to the Supported Platforms section of the Oracle Revenue Management and Billing Installation Guide for Oracle WebLogic versions supported). This server can be run on a variety of supported Linux and UNIX platforms (Refer to the Supported Platforms section of the Oracle Revenue Management and Billing Installation Guide for operating systems and versions supported). Within the business application server, the following components are implemented:
 - Business Objects The business logic for each object in the system is expressed as a Java object. It contains all the SQL, programmatic rules, and structures to manage the data for the transactions.
 - OBB Connection Pool If any database access is required, we use an industry component called Universal Connection Pool to manage and pool the connections to the database for the batch component and use the Oracle WebLogic's own native JDBC-based data source connection pooling for the online and web services component. This will reserve connections and ensure efficient use of connections to the database. To access the database product uses the Oracle Database Client provided to ensure correct connection. These clients are multi-protocol for maximum flexibility.
- Database Server The Oracle Database used for the implementation is implemented in the
 database server. The product supports several database versions (Refer to the Supported
 Platforms section of the Oracle Revenue Management and Billing Installation Guide for database
 versions supported). The database server only stores and retrieves the data for the product as all
 the business logic is in the business objects.
- Batch Server In some cases, processes need to be processed in bulk and in the background. The Batch Server is a set of JVM's clustered using Oracle Coherence. This feature supports multithreaded background processes processing records in bulk across a cluster (BATCH).

Note: The Oracle Coherence implementation is embedded in ORMB and is restricted to the background processing component only. Implementation of other Oracle Coherence features beyond that provided with the integration requires the purchase of a full Oracle Coherence license.

1.1 Roles and Features

Each tier in the architecture has a specific role in the operation of ORMB. The sections below outline the roles and features of each tier.

1.1.1 Browser Client

The Browser User interface (BUI) is a combination of HTML, Javascript, and Oracle Jet for creating interactive Web applications. This makes web pages more responsive by exchanging small amounts of data with the server, so that the entire page does not have to be reloaded each time the user makes a change. This increases the Web page's interactivity, speed, and usability.

Note: Refer to the *Oracle Revenue Management and Billing Installation Guide* for the supported browsers and the supported versions of those browsers.

In past releases, Adobe/Apache Flash Player was required for displaying and interacting with graphs. This is no longer required.

There are no ActiveX or Java components in the base product installation. This means that the deployment of the browser client is relatively simple as the only required component to use the product is a supported version of a web browser on the client machine. If the implementation requires ActiveX controls for extensions, then they can be added and used for the implementation.

The browser tier for the ORMB application is provided for the end users to access the product on a desktop. The client provides the following roles in the architecture:

- Screen Rendering and Caching All the screens are rendered using standard HTML and JavaScript (not Java). The rendering is performed as the screen is served from the web application server and stored in the local browser cache.
- **User Interaction** The client provides the user with the screen interaction. Once the page is rendered the user can interact (manipulate data and screen elements) in accordance with their business transaction. The browser client is responsible for ensuring navigation and interaction with the user interface elements.
- User Context The product is stateless and therefore the client stores the transactional context
 locally and passes this to the transaction as required. The client records the context of the
 transaction in the browser memory.

No business logic is stored on the client component.

1.1.2 Web Application Server

Oracle Revenue Management and Billing is a set of Oracle WebLogic Web applications that are housed in an Oracle WebLogic domain. The product and the web application server provide the following roles in the architecture:

- **Authentication** The web application server software that houses the product provides adapters to common security repositories. This means that security products interfaced to the web application server software can be used in conjunction (with configuration) with the product.
- Managing Client connections The web application server software manages any client connections (during and after they are authenticated) for processing and availability.

- Page Server The major responsibility of the web application server is to serve pages to the client
 on demand. At start-up time (or at the first request for a particular page) the product generates
 the screens dynamically using metadata and rendering style sheets. These are cached for reuse
 locally.
- Cache Management For performance reasons, the static data (usually metadata and configuration data) is cached in memory on the web application server.

No business logic is stored on the web application server component. The web application server Component of the product is written in Java and JavaScript.

1.1.3 Business Application Server

Oracle Revenue Management and Billing is a set of business applications that are housed in Oracle WebLogic (this can be the same instance of the web application server or a separate one). The ORMB application and business application server provide the following roles in the architecture:

- Authorization After authentication has been performed by the web application server, the business application server is responsible for determining which functions and which data can be accessed.
- **Data Integrity** The business application server contains the business logic to maintain referential integrity for the product data.
- **Validation** The business application server contains the business logic that contains all the validation rules for the product data.
- **Business Rules** The business application server contains the business logic that implements business rules and performs calculations.
- **SQL** The business application server contains all the SQL statements and formats and processes results from those SQL statements.

The business application server Component of the product is written in Java.

1.1.4 Database Server

Oracle Revenue Management and Billing contains a database schema within a database management system. The database server has the following roles in the architecture:

- **Data Storage** The database is responsible for efficiently storing all data.
- **Data Retrieval** The database is responsible for efficiently retrieving data using SQL provided by the business application server.
- Data Management The database is responsible for efficiently managing all data.

No business logic is stored on the Database Server.

Note: Refer to the *Oracle Revenue Management and Billing Database Administrator's Guide* for the ORMB application specific facilities supported by the Database Server.

1.1.5 Batch Server

Oracle Revenue Management and Billing is known for its online (or foreground) processing (a.k.a. online processing) but one of the major features of the product is its set of background processes. Background processing is a major part of the product with numerous background processes supplied as standard.

The easiest way to understand the concept behind background processing is to think that background processing is like a super-efficient user that operates on a batch of objects. That is why background processing is commonly called Batch.

Note: For publishing purpose the term batch may also be used to denote background processing in this document.

Online typically operates on one object at a time, initiated by an online user or a web service call, where batch can operate on one or more objects (also known as a set of objects) at a time, initiated using several technologies.




Figure 2: Batch Processing Architecture

The main reasoning behind the super-efficient user is that each background process consists of a driver object that identifies the set of valid objects to process and then processes each object through the same business objects that the online uses. For example, the **BILLING** driver determines which accounts are eligible to be billed according to business calendar and then passes each account to the rate object to produce a bill. Contrast this with online bill generation, where the user identifies the account manually, and then that single account is passed to the same rate object to be billed. The background process can call more than one object during the duration of the background process.

For the batch process, all the database access and object access (including access to business objects, algorithms, user exits (server side only) etc. is done through the Oracle Utilities Application Framework.

1.1.5.1 Background Processing and the Architecture

The Background Processing component is run within the Oracle Utilities Application Framework and is associated typically with the business application server. It is not associated with the web application server nor requires it to be active to operate. The only component other than product that the background processing component requires is the database server (or tier).

Depending on the initiation method employed, the background processing component uses a standalone copy of the product to perform access to the database and business objects and its own copy of the same business objects used by the business application server.

Essentially the background processing has its own resources (Java Virtual machines (JVMs), connection pools) independent of the rest of the architecture and can therefore be run on the same hardware as the rest of the architecture or on dedicated hardware.

1.1.5.2 Batch Architecture Overview

The background processing component of the architecture is a scalable clustered batch approach that allows implementation, using configuration, to spread the batch load across a clustered based architecture.




Figure 3: Batch Architecture Overview

The architecture has the following features:

A background process cluster is defined using the inbuilt Oracle Coherence configuration. This
cluster defines the group of hosts, either communicating via unicast or multicast, which will
execute background processing threads.

Note: The Oracle Coherence implementation within the product uses a subset of the Oracle Coherence feature set, specifically Named (or Job) Caches.

- Within the cluster, the configuration defines threadpoolworkers (also known as workers). These
 are running Java Virtual machines where the batch processes are executed. Threadpoolworkers
 are named to segregate batch threads and can be clustered across hosts defined in the Coherence
 cluster. Threadpoolworkers are defined with a maximum limit on the number of threads
 supported per instance of the threadpool.
- Background processes are submitted (known as submitters) to the named threadpools either at a
 particular threadpool/host instance or automatically distributed across a threadpool across the
 cluster.
- A background process is defined within the metadata as a batch control (see <u>Batch Controls</u>) which
 defines the physical characteristics of the job as well as any configurable parameters of the
 background process.
- When a background process is executed, several threads (1 to many) are specified in the
 execution. Each thread will create Batch Instance records to track the progress of the job internally
 (exposed through the Batch Run Tree transaction within the product).
- Oracle Coherence is used, internally, to manage the communication between the cluster and all
 the members (such as workers and submitters) within that cluster. If a submitter or workers
 completes the thread or aborts, then the cluster is informed and synchronized to take this into
 account. For instance, in the case of a status change (Completion or abort) the Batch Instance
 record is updated to reflect the state of the job.

2. Concepts

Before you attempt to configure or operate Oracle Revenue Management and Billing, there are important concepts that you should understand. These concepts are addressed in this document as a basis for the content of the technical documentation.

2.1 Environment

In a product implementation and post-implementation, there will be several copies of the product installed. Each copy of the product is known as an environment. Each environment will be created for a specific purpose, according to your site plans, and accessible to a group of users deemed necessary for that purpose. For example, there will be at least one testing environment where designated personnel will perform their testing tasks.

For planning purposes, an environment is an instance of:

- The Web applications deployed in an Oracle WebLogic domain. This may be in a single server or across a cluster of servers.
- The business applications deployed in an Oracle WebLogic domain. This can be the same physical Oracle WebLogic Server or another instance (such as a separate server). This may be in a single server or across a cluster of servers.
- A database containing ORMB application schema. Physically, a schema can exist in an individual
 database instance or shared within a database instance (i.e., you can install multiple schemas of
 the product in the same database). This may be in a single server or across a cluster of servers.

While there is no restriction on the number of environments it is recommended that the minimal number of copies of the product is installed using the guidelines outlined in the *Environment Management document* in the *Software Configuration Management Series* (Document ID: 560401.1) on My Oracle Support.

2.1.1 Environment Identifier

As part of an installation an environment identifier is generated for the installation. This identifier is used by the technical utilities to manage the components and servers across the architecture. The environment identifier is used in the following ways:

- The Oracle Application Management Pack for Oracle Utilities uses the environment identifier to link child targets to the Utilities Environment target. This is used for monitoring and managing disparate targets (within a single host or across multiple hosts).
- It is used for tracking purposes only outside of the Oracle Application Management Pack for Oracle Utilities.

This feature is used in conjunction with the Server Roles facility.

2.1.2 Server Roles

One of the features of the installation and configuration is the ability to design architecture roles to a single installation (i.e., a product home). This allows the product to support specific roles per installation or a combination of roles for a single installation for flexibility. There are three roles available to be used:

Role	Usage
batch	This installation will use the batch server functionality
integration	This installation will use the web service functionality
online	This installation will use the online functionality

Selection of each of the roles will enable or disable certain parameters that are available in the configure Env.sh (see configure Env – Set up Environment Settings) utility.

Note: Even though the role can be set for individual sets of functionalities, all the code and facilities are installed and patched to support post installation role change.

If the role is changed post installation additional parameters may need to be provided.

Once the role is set several additional configuration parameters are set in the ENVIRON.INI:

- <u>SERVER_ROLE_BATCH</u> (see <u>SERVER_ROLE_BATCH Whether the Batch Server Is Enabled in this Installation</u>)
- <u>SERVER_ROLE_INTEGRATION</u> (see <u>SERVER_ROLE_INTEGRATION</u> Whether the IWS Server_Is Enabled in this Installation)
- <u>SERVER_ROLE_ONLINE</u> (see <u>SERVER_ROLE_ONLINE</u> Whether the Online Server Is Enabled in this <u>Installation</u>)

2.2 Administration User ID and Group

Prior to installing the ORMB application, you create a UNIX administration User ID and administration group. This account is used to install and operate the product. The administration User ID and product group are provided as parameters during the installation process. By default, the product administration User ID is splsys (SPLADMIN parameter and environment variable) and the group is splusr (SPLADMINGRP parameter and environment variable). However, alternative values can be used according to your site standards.

The administration User ID is responsible for the following:

- It is the owner of all the files installed for the ORMB application.
- It is the only User ID that should be used to run any of the administration tools provided with the ORMB application.
- It is the User ID that owns the UNIX resources used by the ORMB application. When the product is running, this User ID owns the processes associated with running the base software.

The administration User ID should be protected from unauthorized use. If components of the responsibility of administration need to be delegated to other users on the machine, we recommend not giving out the administration User ID. Instead, an alternative solution may be sought (such as using sudo or similar security tools).

The administration User ID should not be used for any of the following:

- As a product end user. By default, the administration User ID does not have access to the functionality of the ORMB application.
- To run product background processes.
- To manipulate data files exported from or imported into ORMB application from any interfaces.

This technical document will refer to the administration User ID as splsys. If your site uses an alternative User ID as the administration User ID, substitute that User ID value for splsys.

Implementation Tip: It is possible to implement a different owner per environment in the product. Why would you want to do this? If you want to allow developers or testers to restart environments themselves, you can give access only to appropriate environments to distribute the administration. This can be achieved by installing the ORMB application with different User IDs. You must log in and administrate each environment with its account only.

2.3 Native Support

Note: From Oracle Utilities Application Framework Version 4.3.0.5 and above, only native installation support is provided for Oracle WebLogic. There is no option for embedded mode installation.

In the native mode, the ORMB application is deployed to the Oracle WebLogic domain location using the Oracle WebLogic deployment tools and managed from the console. In this mode the product runtime for the product is either embedded in the EAR files or referenced indirectly by the EAR file. The domain files exist under the Oracle WebLogic installation location, as other Oracle applications use. The product files are deployed to the Oracle WebLogic location using the deployment utilities provided by Oracle WebLogic (console or WLST can be used). This means that all the administration for any Oracle WebLogic configuration can be performed from the console rather than from command lines and configuration files.




Figure 4: Native Architectures

Note: For native installation instructions refer to the <u>Native Installation Oracle Utilities Application</u> <u>Framework</u> (Document ID: 1544969.1) available from <u>My Oracle Support</u> and <u>Oracle Revenue Management and Billing Installation Guide.</u>

2.4 Directory Structure

To facilitate upgrades and ease maintenance, Oracle Revenue Management and Billing installation process creates a very specific directory hierarchy under the administration User ID of splsys (by default). The structure holds all the code, system products, scripts and temporary files that are created by the product during installation and operation.

Points to Note:

Every part of Oracle Revenue Management and Billing relies on the fact that this directory structure and the files within remain intact as delivered.

At no time should you modify any of the supplied programs or scripts without the express direction of Oracle.

There are two different directory structures that the product application uses:

- Base code directory structure (denoted in this documentation as <SPLDIR>)
- Application output directory structure / log directory (denoted in this documentation as
 <SPLDIROUT>)

Within each of the structures, there is a mount point and a subdirectory for each environment <environment> installed on the machine. The base mount point <SPLDIR> contains the environment directories that hold all the application software for each environment. The application output mount point <SPLDIROUT> contains the environment directories that hold temporary files (such as the output batch) as well as batch log files. The default <SPLDIR> directory is /spl and the default <SPLDIROUT> directory is /sploutput.

When a user logs on to an environment of ORMB either using the browser- based interface or directly on UNIX/Linux, the environment is set up (i.e., environment variables, and so on) to point to the appropriate directory structure under the mount point. The environment variable that points to an environment directory under <SPLDIR> is \$SPLEBASE. The environment variable that points to an environment directory under <SPLDIROUT> is \$SPLOUTPUT. The SPLEBASE and SPLOUTPUT environment variables are two of the standard environment variables used by the utilities provided with the product and runtime.

Implementation Tip: The actual location of the application directory **<SPLDIR>** and application output directory **<SPLDIROUT>** is up to site standards. The product does not care where it is installed as it internally uses the environment variables to access the correct locations.

The actual location for the mount points can differ per environment if you want. This is handy if you need to vary the location because you do not have enough space for all your non-production environments. Typically, the number of environments during an implementation varies according to the level of access and desired amount of testing and training. The only restriction is that there can only be one location for **SPLEBASE** and **SPLOUTPUT** per environment.

2.5 Software Directory Structure

The following components are stored in the base code directory structure:

- Runtimes for Components All the runtime executables for the base software.
- Business Object Binaries All the binaries that contain the business logic.
- Configuration Files All the configuration files for the business objects and runtimes
- Scripts Any administration or runtime scripts that are supplied to the customer.
- **Supported Plug-ins** Source and executable for supplied plug-ins.

The following table outlines the typical contents of these directories:

Directory	Contents
bin	Utilities and commands for operations and configuration.
etc	A set of directories holding configuration files used in the product as well as template files and base libraries used to generate the configuration files.
Java	Location of temporary files for java execution.
Ks	Location of Key Stores
oem	Application Management Suite for Oracle Utilities generated files
	Note: Files in this directory are generated by the discovery process used with the Oracle Application Management Pack for Oracle Utilities.
logs	Location of product specific log files
osbapp	Oracle Service Bus integration (optional)
product	Directories containing any bundled software with the product.
scripts	Directory containing any implementation specific scripts.
soaapp	Oracle SOA integration (optional)
splapp	Directories containing the JEE Web Applications (see SPLApp).
structures	Internal structures used for configuration utilities.
templates	Base templates used to build configuration files.
tmp	Directory used to hold intermediary files used for the deployment process.
tools	Location of service pack, single fix, and group fix utilities. See <u>Tools</u> .
updates	Location of installed_fixes.txt.
	Note: The updates directory only exists after at least one patch has been installed. If the directory does not exist, then no patches have been installed on this environment.

2.5.1 Software (splapp) Directory

Under the splapp subdirectory for each environment, there are several subdirectories:

Directory	Contents
applications	Location of the Web application product files
billview	Location of the online bill viewing files (Products supporting bill view only)
businessapp	Location of the business application product files
certs	Location of security certificates
config	Location of temporary configuration files
iws	Location of Native Web Services
pending	Internal use only
standalone	Location of common Java libraries and the batch component of the product
tpw	Location of threadpool worker specific files
xmlMetaInfo	Location of the service definitions for the product

Warning! Under no circumstances should files be manually altered in these directories unless instructed by Oracle Support. The Oracle Utilities SDK will deposit files in the relevant locations in this structure using the Packaging component of the SDK or using the Development tools directly.

2.5.2 Tools Directory

Note: In past releases the utilities to install patches were included in each patch. This is not the case anymore as they are centralized as part of the installation.

These utilities are not usually executed manually but are part of general installations and automation from Application Management Pack for Oracle Utilities.

The tools directory is used for deployment and patching tools used by Application Management Pack for Oracle Utilities and the internal patching utilities. The directories are in the following structure:

Directory	Contents
bin	General Software patching utilities
bin/db	Database Patching utilities
bin/db/bin	Binaries for patching
bin/db/config	Logging configuration for patching utilities
bin/db/lib	Java Libraries for patching utilities
domaintemplates	Oracle WebLogic Domain Templates for product

2.5.3 Directory Permissions

The directories within the ORMB application are controlled by the operating system security relating to the administration user assigned to the product. The table below outlines the permissions under the \$SPLEBASE location:

Directory/Files	Owner	Group	Other
etc	rwx	r-x	
Individual files	rw	r	
logs	rwx	rwx	
logs/system	rwx	rwx	
Individual log files	rw	r	
Oracle WebLogic Configuration Files	rw	r	
Oracle WebLogic shell scripts (.sh)	rwx	r-x	
product	rwx	r-x	
product/apache-ant/bin/ant	rwx	r-x	
scripts, tools, updates	rwx	r-x	
Shell scripts (.sh) in bin	rwx	r-x	
osbapp, soaapp, splapp	rwx	r-x	
structures	rwx	r-x	
templates	rwx	r-x	
tmp	rwx	r-x	

Legend:

- r = Read Only
- rw = Read Write
- rwx = Read/Write/Execute
- rx = Read/Execute
- blank = No permissions

These permissions are set by the setpermissions.sh utility which is executed as outlined in the Oracle Revenue Management and Billing Installation Guide.

2.6 Output Structure

The application's processes (batch and online) that produce output and logs place information in this directory structure. The environment directories are referenced by the environment variable **SPLOUTPUT**. By default, this directory is created as /spl/splapp, though this can be substituted for an alternative during the installation process. The table below illustrates the typical directory structure for this location:

Directory	Contents
logs/system	Directory containing application logs files. This is independent of web application server, Business Application Server, and Database Server log files.
logs/backup	Default location of backup of logs if <u>SPLBCKLOGDIR</u> is set.

The implementation may add subdirectories as their site standards and implementation dictates.

2.7 Environment Variables

Your application uses several environment variables to determine where information is stored and to be placed for its internal operations. Becoming familiar with these variables will assist you in finding information quickly and efficiently.

Note: If a custom script is written to access or write information to the product functionality, it is highly recommended that the following variables be referenced in your scripts. This is to maximize the chance that your script will remain functional across upgrades.

The following table outlines some of the key environment variables:

Variable	Usage
ANT_ADDITIONAL_OPT	Options for ant as per the configuration settings at installation time
ANT_HOME	Location of ant build utilities
ANT_OPTS	Options for ant for Oracle SDK
ANT_OPT_MAX	Maximum memory settings for ant as per the configuration settings at installation time
ANT_OPT_MIN	Minimum memory settings for ant as per the configuration settings at installation time
CMPDB	Database Type (ORACLE)
DBNAME	Database Name
ENVFILE	Location and name of environment configuration file
HIBERNATE_JAR_DIR	Location of Hibernate Java library
HOSTNAME	Name of host (fully qualified)

Variable	Usage
JAVA_HOME	Location of JDK
LD_LIBRARY_PATH	Library Path
NLS_DATE_FORMAT	Oracle NLS Date Format
NLS_LANG	Oracle NLS Language string
NLS_SORT	Oracle <u>NLS</u> Sorting
ONLINEBILLINI	Location of document rendering software template building configuration files
ONLINEDOCINI	Location of document rendering software configuration files
OPSYS	Operating System Name
OPSYSINFO/OPSYSVER	Operating System Version
ORACLE_CLIENT_HOME	Location of the Oracle Client software (used for location of perl). If full Oracle Database software is installed on the host, this value will match ORACLE_HOME
ORACLE_HOME	Location of the DBMS software
OSTYPE	Operating System Type
PERL5LIB/PERLIB	Location of Perl Libraries
PERL_HOME	Location of Perl
SERVER_ROLES	Roles enable for this server
SERVER_ROLE_BATCH	Whether the batch server is included
SERVER_ROLE_INTEGRATION	Whether the integration server is included
SERVER_ROLE_ONLINE	Whether the online server is included
SPLADMIN	Administration User ID
SPLADMINGROUP	Administration group
SPLApp	Name of root Web application WAR file.
SPLAPP	See SPLOUTPUT
SPLBCKLOGDIR	Location of backups of online log files (must be set manually)
SPLEBASE	Location of software for environment
SPLENVIRON	Name of environment
SPLOUTPUT	Location of output for environment
SPLRUN	Location of runtime for environment
SPLSDKROOT	Location of SDK (Development environment only)
SPLSYSTEMLOGS	Location of product specific logs

Variable	Usage
SPLVERSION	Version identifier of product (prefixed with V)
SPLVERSION_NUM	Version number of product
WEB_ISEXPANDED	Whether Web application is expanded or not (not = WAR/EAR files)
WEB_SERVER_HOME	Location of Web Application Server software
WL_HOME	Location of Oracle WebLogic installation (WebLogic supported platforms only)

Note: If a custom script is written to access or write information to the product functionality, it is highly recommended that the following variables be referenced in your scripts. This is to maximize the chance that your script will remain functional across upgrades.

HIBERNATE_JAR_DIR is used for the installation process only. After installation is complete the jar files located at the locations specified by these environment variables are copied to the correct locations for execution.

Additional variable may be created by various operating system and product utilities. The list above constitutes the non-temporary variables.

2.8 Common Application Logs

When the application is operating the infrastructure logs messages within its own logs. For example, the database will log database errors or messages to the database logs, Oracle WebLogic will log web application errors or messages to the Oracle WebLogic server logs and so on. The name and location of these logs is set by relevant vendors of those logs. Refer to the documentation provided with that software on where logs are stored and their logging conventions.

Additionally, the application writes several application specific logs to \$SPLSYSTEMLOGS. Some of these logs are further classified into technical and user logs. As the name suggests, the technical logs contain tracing information for SQLs, stack traces of Java code and other similar technical traces. Essentially, these are errors that suggest the system is misconfigured or is being run in a way that is not expected and contain Application Trace Data which is required for diagnostic purposes. Whereas the user log consists of a Business logic messages, Business trace data. The following are the logs:

- spl web-tech.log Web application server application messages that are technical in nature.
- spl_web-user.log Web application server application messages that contain user/business data or traces.
- spl_service-tech.log Technical messages for the business application server. If the business application server exists on the same Oracle WebLogic Server instance (i.e., as per a local install) as the web application server for an environment then this log does not exist and all messages are written to the spl_web-tech.log.

- spl_service-user.log Business logic/trace messages for the business application server. If the
 business application server exists on the same Oracle WebLogic Server instance (i.e., as per a local
 install) as the web application server for an environment then this log does not exist and all
 messages are written to the spl_web-user.log.
- spl_iws.log Web Services Adapter messages.
- Background processing logs are also categorized into technical and business logs and are in \$SPLOUTPUT for the following:
 - threadpoolworker.
 datetime>-tech.log The threadpoolworker technical log for threadpool
 started at datetime>.
 - threadpoolworker.
 threadpool
 .
 datetime
 user.log The threadpoolworker business log for threadpool
 threadpool
 started at
 datetime
 - ..
 ..
 ..
 .
 ..
 ..
 .
 ..
 <a

The format of all logs is as follows:

Field	Comments
<userid></userid>	User ID of transaction (blank or "-" for system generated messages)
<transactionid></transactionid>	Transaction Identifier
<ecid></ecid>	Execution Context Identifier (weblogic)
<date time=""></date>	Time of transaction in format YYYY-MM-DD HH24:MM:SS,SSS
<threadinfo></threadinfo>	Information of the thread
<log level=""></log>	Logging Level enabled
<class></class>	Java class generating message (see Javadocs in appViewer) (applicable for tech logs)
<message></message>	<message contents=""></message>

Sample log entries:

User Application Error logs:

SPLRXO - 364812-788-1 2016-11-16 13:08:44,371 [[ACTIVE] ExecuteThread: '13' for queue: 'weblogic.kernel.Default (self-tuning)'] INFO (support.changehandlers.ChangeEventHandler) PK1 PK2 combination not found. Check if the fields are populated. Message Number 11001, 402.

Tech Application Error logs:

SPLRXO - 364812-788-1 2016-11-16 13:08:44,371 [[ACTIVE] ExecuteThread: '13' for queue: 'weblogic.kernel.Default (self-tuning)'] INFO (support.changehandlers.ChangeEventHandler) The following rule was violated: Characteristic Value should be valid: userCharacteristic:Characteristic Value should be valid for entity 'F1US'

2.9 Batch Concepts

Note: The **DISTRIBUTED** mode, supported in previous versions of Oracle Utilities Application Framework applications has been removed. Customers using this mode should migrate to **CLUSTERED** mode using either a single server configuration (ss) or unicast configuration (wka) using <u>Bedit</u> (see <u>Configuring Batch</u> Using Bedit)

The batch component of the architecture has several key concepts to understand.

2.9.1 Batch Clustering Concepts

As mentioned in the previous section, Oracle Coherence is used internally to cluster the resources needed for the batch architecture. This is similar in concept to a cluster used by the JEE web application server for online and web services.

- A cluster is one or more hosts that can execute batch processes. A cluster is named to delineate it from other clusters in your network. Oracle Coherence Named Caches are used to implement the cluster.
- Members of a cluster are hosts, threadpools and submitters. Each member is tracked by the cluster for high availability. At least one member must be active for a cluster to operate.
- Intracluster communication between members of the cluster can be achieved using uni-cast (also known as Well Known Addresses) or multi-cast.
 - In uni-cast implementations, each host and associated port is defined in the cluster. Each
 cluster member has definitions of other members. This mode is a less dynamic
 configuration but optimizes host to host communications for large clusters.

Points to Note:

As each member must have its own configuration. To add or remove members requires manual synchronization of **configuration** files.

Large clusters have many hosts, large number of threadpools and/or large number of threads executing at the same time.

- In multi-cast (default) implementations, a multi-cast address and port are defined across the cluster which members attach to when executing. This mode is dynamic but traffic across nodes can be excessive for large clusters.
- A threadpool is a Java Virtual Machine (JVM) that executes batch threads. It is a long running JVM
 that batch threads are submitted to. Threadpools are named to group resources across a cluster
 when using multiple instances of a threadpool.
- A threadpool has a configurable maximum capacity for running batch threads to prevent overloading of JVM's. Running multiple instances of a threadpool (within or across hosts) can increase the limit and implement high availability.

Note: Threads in background processing are typically heavier in terms of resource usage than typical Java threads hence lower thread limits.

- Clusters can support dedicated cache threadpools. In a cluster, each member can potentially
 communicate to each other member. In a large network this can cause network overheads that
 can adversely affect performance. To minimize the impact of network traffic, it is possible to
 configure a cache threadpool that will act as a central co-ordinator in the cluster to optimize and
 channel intramember communication.
- Clusters can support administration threadpools. In a cluster, it is possible to check on the status, in real time using JMX, across the cluster by connecting to any node in the cluster. It is possible to set up an administration node that can act as a single point of contact across the cluster to monitor performance, in a similar vein as the administration server in the JEE architecture. These administration threadpools can be used by command line utilities, jconsole, Oracle Enterprise Manager through Application Management Pack for Oracle Utilities and/or Coherence Management Pack.
- Submitters are instances of individual background processes or individual threads of background
 processes that are submitted to a named threadpool. The submitter waits for the thread or
 background process to complete or abort and reports the status of the thread or background
 process to the operating system. This latter facility is used by Batch Scheduling tools to determine
 the status of the background process.
- Submitter can be targeted to specific instances of a threadpool or submitted to the cluster of threadpools. Submitters can execute specific threads or all threads in a single execution.

2.9.2 Batch Controls

Note: The system is delivered with all necessary batch controls for the supplied base background processes.

Background processes within the ORMB application must be defined using metadata (as well as physical code) to execute the process in the architecture. Refer to the online help and user documentation for details of the attributes associated with a batch control.

2.9.3 Standard Parameters

To standardize all the background processes, the ORMB application uses several common standard parameters to uniformly provide functionality across all processes. The table below lists all the standard parameters:

Parameter	Usage
Batch code	Code is the unique identifier of the background process
Batch thread number	Thread number is only used for background processes that can be run in multiple parallel threads. It contains the relative thread number of the process. For example, if the billing process has been set up to run in 20 parallel threads, each of the 20 instances receives its relative thread number (1 through 20).

Parameter	Usage
Batch thread count	Thread count is only used for background processes that can be run in multiple parallel threads. It contains the total number of parallel threads that have been scheduled. For example, if the billing process has been set up to run in 20 parallel threads, each of the 20 instances receives a thread count of 20.
Batch rerun number	Rerun number is only used for background processes that download information that belongs to given run number. It should only be supplied if you need to download an historical run (rather than the latest run).
Batch business date	Business date is only used for background processes that use the current date in their processing. For example, billing using the business date to determine which bill cycles should be downloaded. If this parameter is left blank, the system date is used.
Commit Interval	Override maximum records between commits. This parameter represents the number of transactions that are committed in each unit of work. This parameter is optional and overrides the background process's Standard Commit between records (each background process's Standard Commit between records is documented in the product documentation). You would reduce these values, for example, if you were submitting a batch process during the day and you wanted more frequent commits to release held resources. You might want to increase these values when a background process is executed at night (or weekends) and you have a lot of memory on your servers.
Application Service	This is the application service that is associated to the batch. All the users who are allowed in the application service which is associated with a particular batch control will be allowed to submit the batch job.
Language	This is the language code used to retrieve messages and format output from background processes.
Traces	 Trace program at start (Y/N), trace program exit (Y/N), trace SQL (Y/N) and trace output. If trace program start is set to Y, a message is displayed whenever a program is started. If trace program at exit is set to Y, a message is displayed whenever a program is exited. If trace SQL is set to Y, a message is displayed whenever an SQL statement is executed. If trace out is set to Y, message is output from the program at execution points. Note: This facility should only be used in development.
	The state of the s

2.9.4 Additional Key Parameters

In all batch controls there are two additional parameters that may not be specified in the batch control definition but are available for use within each job:

- MAX-ERRORS (maxErrors) This is the error tolerance for the job. When the number of errored
 records in a thread for a job has been exceeded that thread is stopped with an appropriate error
 code. This setting is to prevent large amounts of errors to influence the state of the job.
- **DIST-THD-POOL (threadpool)** This allows an indvidual pool to be specified for the execution of the job. This is primarily used with online submission.
- emailMode Defines the status for which an email notification is sent when a job ends. This does not apply to individual threads but when all threads are complete. Valid values are:
 - o **ERROR** Send an email when at least one thread ends in error status.
 - o **SUCCESS** Send an email when all threads end successfully.
 - o ALL (Default) Always sends an email when all threads end regardless of status.

Note: This is used for online submission when an email address is provided on the job submission and the email server is configured.

- overrideLowIdValue Specifies a new low id to use in calculating the range for a thread. The ORMB application, by default, assumes that the ID is between 0's (for example, 000000000) and 9's (for example, 999999999), but this parameter will override the low value. The product calculates each thread's low and high id by slicing the job's range into chunks using the thread number and count. It is typically more appropriate for sequentially allocated IDs to evenly distribute work among threads. The parameter value can be an actual number, or it can be set to auto. If the parameter is set to auto, then the value is set to the lowest current value on the associated database table. The table name is determined from the batch program's query iterator.
- overrideHighldValue Specifies a new high id to use in calculating the range for a thread. The ORMB application, by default, assumes that the ID is between 0's (for example, 000000000) and 9's (for example, 9999999999), but this parameter will override the high id. The product calculates each thread's low and high id by slicing the job's range into chunks using the thread number and count. It is typically more appropriate for sequentially allocated IDs to evenly distribute work among threads. The parameter value can be an actual number, or it can be set to auto. If the parameter is set to auto, then the value is set to the highest current value on the associated database table. The table name is determined from the batch program's query iterator.
- idRangeOverrideClass Provides for a custom class to do thread range calculation. The class name specified must implement interface com.splwg.base.api.batch.BatchldRangeOverride.
 During batch execution, this override class will be instantiated, and the setter methods called to initialize the IDs as required. The low and high getter methods will be called to retrieve the high and low ids to be used for the run.
- numRecordsToFlush Defines how frequently to flush the Hibernate cache to prevent high heap consumption and OutOfMemoryErrors. In SingleTransactionStrategy there are no commits throughout the run, so this parameter can be used to flush the Hibernate cache periodically. This parameter is only applicable to jobs that use SingleTransactionStrategy.

Note: The parameters overrideLowldValue and overrideHighldValue are only applicable to jobs that use ThreadIterationStrategy.

These parameters may be added to the Batch Control or properties files used for running the job.

2.9.5 Batch Run Tree

Within the ORMB application's browser interface, there is an ability to monitor the status and outcomes of individual processes. This can be useful for finding out what actually occurred if an error condition occurred. Refer to the online help for more information about this facility.

• The **Batch Run Tree** is available to any valid user and is a method to communicate the execution information to the relevant business representatives.

2.9.6 Timed Jobs

Note: Monitor processes are ideal for Timed Jobs.

By default, background processes start and finish when they have processed the records it has selected at the start of execution. In this case, to process more records it is necessary to run the batch process again.

In some business processes, it may be necessary to continually execute a job to process work that is ready at any time. For example, processing payments, meter reads, asset changes or tasks as they appear. This situation is handled as a Timed Job. This batch control type is configured with a Timer Interval (the desired runtime between executions in seconds) and a Timer Active flag (to enable and disable the job activity).

When the Timer Active flag is set to **true**, the product executes the job for the duration of the Timer Interval before executing another instance of the job. This allows the job to run continuously over time, whilst the Timer Active flag is set to **true**.

Each instance of the job will start and stop using the following rules:

- The job will only execute when the **Timer Active** flag is set to **true**. To the next execution from starting this value should set to **false**.
- The job will execute using the parameters on the **Batch Control** including the dedicated parameters for **Timed Jobs** such as User ID, Batch Language and Email Address.
- Once the Timer Interval has been reached, the job will commit after the latest transaction is complete and update the Batch Control is complete or errored (as appropriate).
- The next instance of the process is repeated as above.

Note: Due to varying transaction workloads the time taken may exceed the **Timer Interval**. This situation can be tracked using **Level of Service** if desired.

2.9.7 Level of Service

Note: For backward compatibility purposes, **Level of Service** is in the disabled state and requires configuration of targets in the **Level of Service** algorithm.

One of the features of the background processing architecture is that all executions of a batch control are tracked internally. This is typically expressed in the **Batch Run Tree** for information purposes but can also be used to calculate an indicator of the level of service if desired using the **Batch Control - Level Of Service** algorithm. Algorithms of this type returns one of three levels of service:

• **Disabled** - Batch level of service algorithm is not enabled for the batch control, or no data is available for comparison.

Note: This can occur for the initial execution only.

- Error Indicates that errors were detected. In this case a message is also returned to indicate the issue.
- Normal Indicated when there were no errors or issues detected by the algorithm.

Note: It is possible to write custom **Level of Service** algorithms to compare any appropriate business metric.

2.9.8 Explanation of Commit Interval

The Commit interval parameter is a tuneable parameter to affect the impact of the background processes on the other processes running and prevent internal database errors. In most cases using the defaults will satisfy your site requirements. It is also important to understand their impact to ascertain whether any change is required.

During processing of any background process, a main object is used to drive the process. Each process tables one or more objects to process. For example, billing processes accounts, meter reading processes meter reads or meter events, asset Processing uses assets, workforce processing uses tasks etc. For other processes it is other objects that are considered the main object. This status of the object or status of related transaction data is used to determine when a transaction is complete.

For the Commit interval this concept is important as:

When a certain number of main objects have been processed then a database commit is issued
to the database. This number is the expressed in the Commit Interval. The larger the commit
interval the larger the amount of work that the database must keep track of between commit
points.

Note: The number of records in progress utilizes redo log space so the size of the redo logs in the database and commit interval must be compatible. The higher the commit interval the more redo log space is required.

• At any time in a process a commit for objects processed may be caused by the reaching the **Commit Interval** or the end of the job, whichever comes first.

2.9.9 Explanation of Thread Limit and Thread Number

Note: Optimization discussions for these parameters are covered in the <u>Batch Best Practices</u> (Document ID: 836362.1) available from <u>My Oracle Support</u>.

One of the features of the Oracle Utilities Application Framework is the ability to run background processes using multiple threads.

The threading concept in Oracle Utilities Application Frameform applications is simple. Each thread takes a predetermined slice of the data to work on. The last thread checks if all other threads are finished and updates the status of the batch control records. For example, if you have 10 threads, then each thread takes 1/10th of the work. As each thread is executing it processes its workload and then completes, the last thread executing is responsible for updating the overall process status to indicate completion.

Implementing threading means you have to execute several background processes with an ascending thread number up to the thread limit. For example, if you have a background process with 10 threads, you must run 10 background processes each with a unique thread number between 1 and 10 to complete the background process. Threads can be located on the same machine or different machines. For example, you can run threads 1 to 5 on one machine and threads 6-10 on another.

Note: If there is limited data skew in the data then the threads should finish around the same time. If there is some data skew, then some threads may finish later than others.

To implement multi-threading when you submit a process:

- Specify a thread limit greater than 1 as a parameter.
- Execute a background process for every thread with a sequential thread number up to an including the thread limit. There are a couple of implementation guidelines with threading:
 - Make sure the number of threads is not excessive. You do not want to flood the CPU's.
 - You must submit a process per thread. In some submission methods this is done automatically and in some it is done manually.
 - Threading will increase throughout BUT it will cause higher than usual resource usage (CPU, Disk etc.) as well as higher contention. Excessive threading can in fact cause performance degradation in online as well as background processing. Therefore, the number of threads should not be excessive.

Almost all background processes within the ORMB application support multiple threads (typically the only background processes that are single streamed are extracts and data loads as they involve reading and writing files).

2.9.10 Explanation of Restart and Rerun

Oracle Revenue Management and Billing allows all background processes to be restarted or rerun as required. During the execution of the background process, restart information per thread is stored within framework, like a checkpoint. This checkpoint is performed at the last commit point as dictated by the **Commit Interval** or the **Timeout value** (**Timeout** applies to Oracle implementations only). When a commit is performed, the last commit point is recorded for the execution. If a thread of a background process fails, the database automatically rolls back to the last commit point. The thread can then be restarted from that point automatically or from the start of the data. To indicate the restart, the thread is executed with the same parameters as the original.

Additionally, processes are re-runable. A background process is re-run able when you can specify a specific run number to be re-run as required or specify a specific business date to reprocess. Using a rerun number or a previously used business date are all that is required to rerun a process.

Note: Not all background processes use Run number as a run indicator. Refer to the online documentation for which batch processes are re-runable.

2.9.11 Submission Methods

There are several methods for submission supported by Oracle Revenue Management and Billing.

• Online Submission - This allows testing users to submit batch jobs from the online component. This facility is typically used for non-production environments.

Note: Oracle strongly recommends that online submission is not used for Production environments.

• <u>Command Line Submission</u> - A number of commands are available to start/stop threadpools and jobs from the command line or from a third-party scheduler.

2.9.11.1 Online Submission

One of the most important useful testing or demonstration facilities of the product is the ability to submit batch processes from the online component of Oracle Utilities Application Framework. An authorized user can submit any batch process using an online batch submission page.

The on-line batch submission page enables you to request a specific background process to be run. Refer to the online help for a discussion on how to use the online submission function. When submitting a background process on-line, you may override standard system parameters and you may be required to supply additional parameters for your specific background process. After submitting your background process, you may use this page to review the status of the submission.

Basically, the following process is used to submit background processes using the online submission method:

• The process to be executed is registered online as to be submitted (or queued). This marks the process execution as Pending. When you request a batch process to be submitted from on-line, the execution of the desired background process will result in the creation of a batch run. Just as with background processes executed through your scheduler, you may use the Batch Run Tree page to view the status of the run, the status of each thread, the run-instances of each thread, and any messages that might have occurred during the run.

Note: Your online submission record is assigned a status value so that you may know whether your batch process has been submitted and whether it has ended; however, it will not contain any information about the results of the background process itself. You must navigate to the **Batch Run Tree** page to view this detail.

• A background process is scheduled using the submission daemon that will pick up any **Pending** background process executions and execute them. When you save a record on the batch process submission page, the batch process does not get submitted automatically. Rather, it saves a record in the batch process table. A special background process will periodically check this table for pending records and will execute the batch process. This background process will update the status of the batch process submission record so that a user can determine when their batch process is complete.

Note: At installation time, your system administrator will set up this special background process or configure the scheduler daemon to periodically check for pending records in the batch process submission table. Your administrator will define how often the system will look for pending records in this table.

It should be noted that this special background process only submits one pending batch process submission record at a time. It submits a batch process and waits for it to end before submitting the next pending batch process.

Note: If you request a batch process to be run multi-threaded, the special background process will submit the batch process as requested. It will wait for all threads to complete before marking the batch process submission record as ended.

During execution the status of the execution in the **Batch Run Tree** is updated as well as the original submission screen. If you wish the system to inform you when the background process completes, you may supply your email address. The email you receive will contain details related to the batch process's output; similar to the batch process results you would see from the **Batch Run Tree**.

Note: This assumes that during the installation process, your system administrator configured the system to enable email notification. Your administrator may also override the amount of detail included in the email notification.

To use this facility the following must be enabled:

- The online submission daemon and DEFAULT threadpoolworker is configured using the following parameters:
 - The <u>BATCHENABLED</u> (see <u>BATCHENABLED</u> Whether Online Batch Server is <u>Enabled</u>) setting must be set to true.
 - The <u>BATCHDAEMON</u> (see <u>BATCHDAEMON</u> Whether Online Batch Daemon is <u>Enabled</u>) setting must be set to true.
 - The <u>BATCHTHREADS</u> (see <u>BATCHTHREADS</u> <u>Number of Online Batch Server Threads</u>) setting must be greater than zero.

Note: The default setting for **BATCHTHREADS** is 5 threads. This setting should only be altered if large numbers of testers need to use the DEFAULT threadpoolworker at the same time.

 An external DEFAULT threadpool and daemon is started using the -d Y option on the threadpoolworker (see threadpoolworker.sh - Manage Threadpools) or starttpw.sh (see starttpw.sh - Start Threadpoolworker) command. For example: threadpoolworker.sh -p DEFAULT=5 -d Y

2.9.11.2 Command Line Submission

At a site implementing the Oracle Utilities Application Framework application, the batch processes to be executed to support the business as well as perform expected maintenance on the system needs to be scheduled, managed, and executed from a central point. In most sites, this is done by using a third-party batch process scheduler that controls the scheduling and execution of any batch processes across a site.

To support the use of such a scheduler with any Oracle Utilities Application Framework based product(s) several scripts and related configuration files have been provided to allow the scheduler to execute the process batch processes.

The scripts and configuration files allow for three fundamental facilities that can be used by external scheduling tools:

- The interface is command line based (it can also be invoked using a java-based API see the product javadocs within AppViewer for a description of the interface) which most external scheduling tools support. See the product javadocs for the description of the interface.
- The command-based utilities return a standard return code to indicate the batch process has been successful or has been unsuccessful. Actions dependent on return code within the scheduler can then be configured.
- The logs within the utilities provided are in a common format that can be interrogated by the external scheduler to provide finer grained actions (especially for unsuccessful executions).

For additional advice about interfacing external schedulers with Oracle Revenue Management and Billing refer to the <u>Batch Best Practices</u> (Document ID: 836362.1) whitepaper on <u>My Oracle Support</u>.

The following guidelines apply:

- Any command should execute <u>splenviron</u> (see <u>splenviron Set Environment Variables</u>) prior to execution.
- Threadpoolworkers should be started prior to running any batch job threads using the threadpoolworker (see threadpoolworker.sh - Manage Threadpools) or starttpw.sh (see starttpw.sh - Start Threadpoolworker) command in the scheduler.
- Batch Job threads should be submitted using the <u>submitjob</u> (see <u>submitjob.sh Submit Batch Threads</u>) command.
- If threadpoolworkers need to be shut down the <u>jmxbatchclient</u> -k (see <u>jmxbatchclient.sh JMX batch command line</u>) command should be used.

3. Operations

There are several common operations that a site will perform on the ORMB application. This section outlines the steps involved in these common operations.

Note: This section only applies to the embedded mode installation of the ORMB application. Customers using native mode installations should start and stop servers through the Oracle WebLogic console, WLST or Oracle Enterprise Manager.

3.1 Command Line Utilities

Oracle Revenue Management and Billing includes several command scripts to aid with its configuration and operation. This section provides information about these utilities.

3.1.1 bedit - Batch Edit

Points to Note:

The splenviron.sh utility must be executed before this utility can be used. See <u>splenviron - Set Environment</u> <u>Variables</u> for details.

This facility is only available if **Enable Batch Edit** is set to true in the installation.

To simplify the configuration of batch a new administration facility has been introduced. The **bedit.sh** is provided to guide the administrator through the cluster, threadpool and submitter configuration process using templates.

Command Usage:

bedit.sh [-h] [[-g] [-t arg] [-b arg |-e arg |-l arg |-c |-s |-w] [file]] | [-A]

Command Line Option	Description
-h	Show command usage
h	Show extended help
-g	Generate configuration from the template and exit immediately. The configuration file name may be specified explicitly or implicitly as described under Mutually Exclusive Arguments below.
-t arg	Template to use. Examples: wka for Well-Known-Addresses; mc for Multicast; ss for Single Server. This is optional. The default is determined from be.prefs, be.properties or be.default.properties, in that order

Mutually Exclusive Arguments:

Command Line Option	Description
-b arg	Configure batch code specific properties files. Maintains job. <arg>.properties files.</arg>
-e arg	Configure general submitter mode properties files. Supports THIN and LOCAL execution mode. Maintains submitbatch. <arg>.properties files.</arg> .properties files.
-l arg	Configure threadpool label specific properties files. Maintains threadpoolworker. <arg>.properties files.</arg>
-с	Configure the cluster configuration. Shortcut name for tangosol-coherence-override.xml
-5	Configure the base submitter configuration. Shortcut name for submitbatch.properties.
-w	Configure the base threadpoolworker configuration. Shortcut name for threadpoolworker.properties.
file	The properties file to edit. This must be a valid batch properties or Coherence XML configuration override file. May be used instead of the shortcut forms above and must be the last argument if specified.

Exclusive Argument:

Command Line Option	Description
-A	Generate ALL the base configuration files and exit. Combines -c, -w and -s option. Option -A must be the only option if specified.

Examples:

bedit threadpoolworker.properties

bedit -t wka -c

bedit -c -l cache

Note: For more information about bedit.sh, refer to the <u>Configuring Batch using Bedit</u> section of this guide.

3.1.2 buildJavadocsIndex.sh - Builds Java Docs

Points to Note:

The splenviron.sh utility must be executed before this utility can be used. See <u>splenviron - Set Environment</u> <u>Variables</u> for details.

This utility is only used for development environments where javadocs must be generated for other developers to use and appViewer is installed and deployed.

This utility only works on custom java classes where source is provided with the customization installation and after the customizations have been installed.

The build javadocs utility, buildJavadocsIndex, creates the javadocs for any custom java code for use for development. The utility does the following:

- After the custom java code has been installed using the SDK utilities, the utility generates the javadoc using the associated JDK.
- The utility optionally adds the generated to the javadoc to the product javadoc already installed in appViewer.
- Optionally regenerates the SPLWeb EAR file to update the appViewer.
- If running in embedded mode, the server needs to be restarted to reflect the change. If running in native mode, the EAR file deployment needs to be updated.

Command Usage:

buildJavadocsIndex.sh [-h] [-n]

Where:

Command Line Option	Description
blank	Generate javadocs and update SPLWeb EAR file
-h	Show usage.
-n	Generate javadocs but skip EAR update.

3.1.3 configureEnv – Set up Environment Settings

Points to Note:

The splenviron.sh utility must be executed before this utility can be used. See <u>splenviron - Set Environment</u> Variables for details.

This utility can be used by both embedded and native mode customers. In native mode, some settings need to be specific values to support the native mode. Refer to the *Oracle Revenue Management and Billing Installation Guide* for further instructions on the use for the different modes.

The configureEnv.sh utility is an interactive method for configuring an environment on the system stored in the etc/ENVIRON.INI. This configuration script sets up important parameters used by other scripts within the system. Normally this script is executed without parameters and the current environment (i.e., the environment that you are currently attached to) is configured.

Command Usage:

configureEnv.sh([-a]|[-g])[-i][-h]

Command Line Option	Description
blank	Configure basic configuration options
-a	Configure advanced configuration options
-с	Calculates variables only through silent mode. This refresh <u>ENVIRON.INI</u> from individual changes

Command Line Option	Description
-g	Configure all configuration options (basic and advanced).
-h	Show usage.
-i	Configure Installation options (used for initial installation)

Refer to <u>ENVIRON.INI</u> - <u>Environment Configuration File</u> for more information on the output of this command.

Note: If an unauthorized user attempts to execute this command the following error message is shown: Can't open/configure.log for output.

3.1.4 createDBStandalone.sh - Creates Database Patches

Points to Note:

The splenviron.sh utility must be executed before this utility can be used. See <u>splenviron - Set Environment</u> <u>Variables</u> for details.

This utility is used for patching only. Refer to the patch documentation for more information.

The createDBStandalone.sh utility, assembles all the needed components to allow database patches to be applied from a remote server. This utility creates the jar file named db_patch_standalone.jar containing the following:

- Relevant files in the bin directory needed for the patch.
- Relevant libraries needed for the patch.
- Relevant configuration files needed for the patch.

Command Usage:

createDBStandalone.sh [-h] [-l <location>]

Command Line Option	Description
blank	Performs complete extraction in default location SPLEBASE/tools/dbstandalone.
-h	Show usage.
-l <location></location>	Outputs jar file to the location <location></location> . If you do not specify a location, then it will default to the blank action.

3.1.5 extractCMSourceUNIX.sh - Migrate Code Across Upgrades

Points to Note:

The splenviron.sh utility must be executed before this utility can be used. See <u>splenviron - Set Environment</u> <u>Variables</u> for details.

This utility is only used for extracting development source from one environment to another. This is used for initial migration from Oracle Utilities Application Framework V2.x to Oracle Utilities Application Framework V4.x

This utility only works on custom Java classes where source is provided with the customization installation and after the customizations have been installed.

When migrating from Oracle Utilities Application Framework Version 2.x to Oracle Utilities Application Framework Version 4.x, this utility extracts the source that was retained in the upgrade and reorganizes it to conform to the newer structures used in Oracle Utilities Application Framework Version 4.x. This is used as an initial load only and does not need to be executed again once the reorganization is complete.

The utility does the following:

- Existing code customizations are extracted to a central location.
- The code customization is reorganized into the Oracle Utilities Application Framework Version 4.x format.
- The applyCM utility provided with the Oracle Utilities SDK can then be used to install the customizations on an initial environment as outlined in the Software Configuration Management Series (Document ID: 560401.1) available from My Oracle Support.

Command Usage:

extractCMSourceUNIX.sh -v version -t target [-e] [-l lang] [-h]

Command Line Option	Description
-h	Show usage.
-v version	Version identifier for custom build. This is the build number that is used for CMVERSION.TXT. This parameter is required.
-t target	Directory location for files to be housed. applyCM will be run against this location in future steps. This parameter is required.

3.1.6 initialSetup – Maintain Configuration Settings

Points to Note:

The initialSetup.sh script replaces the gen*.sh script provided with previous releases of the Oracle Utilities Application Framework.

The splenviron.sh utility must be executed before this utility can be used. See <u>splenviron - Set Environment</u> Variables for details.

Warning! This command will reset all configuration files to template settings. Any direct customization to configuration files will be lost. Backup configuration files prior to running this script. If changes are necessary for your site then use <u>user exits</u> (see User Exit Include Files) or <u>custom templates</u> (see Implementing Custom Templates) to retain settings across executions of <u>initialSetup.sh</u>.

During the installation and configuration process several configuration files used by the components of the architecture are built to be used by the various components of the architecture. The utility takes the ENVIRON.INI (see ENVIRON.INI - Environment Configuration File) settings and using a set of provided templates (located in the etc. directory), builds the necessary configuration files for the product components.

This utility has three functions:

- Build/Rebuild the configuration files from templates.
- Build/Rebuild the WAR/EAR files used by the product.
- For customers using native mode, manual redeployment is necessary.
- Build/Rebuild the keystore files.

This concept is shown in the diagram below:




Figure 5: initialSetup Command Structure

While this utility is used at installation time and configuration to reflect configuration settings in the ORMB application, it can also be used to reset the configuration files to the original settings as well as reflect changes to the configuration files.

Command Usage:

initialSetup.sh [-h] [-t] [-w] [-d] [-b] [-y] [-v] [-k] [-f] [-s]

Where:

Command Line Option	Description
blank	Process Templates, Build WAR/EAR files and Deploy to JEE web application server in one process.
-h	Show usage.
-t	Process Templates only
-w	Build WAR/EAR files only
-v	Display Version
-5	Import Key Store from external location (KS_IMPORT_KEYSTORE_FOLDER)
-k	Generate Keystore
-f	Force Task, skipping any warnings (used for silent installs only)

Examples:

\$ initialSetup.sh

100207.02:37:33 <info> Template generation step.

100207.02:37:43 <info> FW template generation step.

100207.02:37:43 <info> Create war file for SPLApp.war.

100207.02:38:26 <info> Create war file for javadocs.war.

100207.02:38:26 <info> Create war file for rest.war.

100207.02:41:11 <info> FINISHED INITIAL INSTALL SETUP at Thu Aug 7 02:41:11 EST 2009

100207.02:41:11 <info> See file /spl/TRAINING/logs/system/initialSetup.sh.log for details

Note: If an unauthorized user attempts to execute this command the following error message is shown: **ERROR:** Could not create a backup of log file.

3.1.7 installSFGroup.sh - Install Software Patches

Points to Note:

The splenviron.sh utility must be executed before this utility can be used. See <u>splenviron - Set Environment</u> <u>Variables</u> for details.

This utility is in the tools/bin directory of the software installation.

This utility does not handle prerequisities unless used with the <u>PatchDeployUtility</u> (see <u>PatchDeployUtility.sh - Create and Deploy Patch Rollups</u>)

This utility only does software installation. Database installation is handled by <u>ouafDatabasePatch</u> (see <u>ouafDatabasePatch.sh</u> - <u>Install Database Patches</u>).

The installSFgroup utility installs a single or group of software fixes that have been downloaded.

Command Usage:

installSFgroup.sh -f InputFile -d InputDir -p product -v version -e splenviron -r splebase -l logfile

Where:

Command Line Option	Description
-f InputFile	Fill path of list of single fixes to install. This can be generated from PatchDeployUtility , included in a service pack, included in a fix, or manually created.
-d InputDir	Location of single fixes downloaded from My Oracle Support. These must be unzipped.
-p product	Product Name for patch file (this is the prefix of the file) (optional)
-v version	Version number of files (optional)
-e splenviron	Environment Name to apply fixes to. Defaults to current SPLENVIRON environment variable if not specified.
-r splebase	Root location of software for environment. Must match value in /etc/cistab . Defaults to current SPLEBASE environment variable if not specified.
-l logfile	Name of log file to output. Defaults to install.log if not specified.

3.1.8 invokeDBUpdatePatch.sh - Regenerates Passwords in Installation Options

Note:

The splenviron.sh utility must be executed before this utility can be used. See <u>splenviron - Set Environment</u> Variables for details.

The invokeDBUpdatePatch.sh utility, updates the Installation options that use encryption for key updates.

It is recommended to refer to the <u>Keystore Configuration</u> (Document ID: 2014161.1) reference paper for details of how and when to use this utility.

3.1.9 iwsdeploy - Inbound Web Services Deployment

Note: The splenviron.sh utility must be executed before this utility can be used. See <u>splenviron - Set</u> Environment Variables for details.

The inbound web services deployment utility, iwsdeploy.sh, creates the web services EAR file and also deploys that EAR file to the servers. The process does the following:

- Extracts the inbound web services that are new or changed as indicated on the deployment record (Needs **Redeployment** status).
- For each web service generates several artifacts required by the web application server to define and execute the web service.
- Builds the components into an EAR file called Webservices.ear located in the \$SPLEBASE/splapp/iws/gen directory.
- Deploys the EAR file to the container configured.

It also is possible to perform this activity using the inbound web services deployment online function. It is recommended that in non-production both methods are available but in production iwsdeploy.sh utility is used.

The iwsdeploy.sh utility does not have any options at the present time.

Command Usage:

iwsdeploy.sh

3.1.10 jmxbatchclient.sh - JMX Batch Command Line

Points to Note:

The splenviron.sh utility must be executed before this utility can be used. See <u>splenviron - Set Environment</u> <u>Variables</u> for details.

For more examples of usage of this command refer to the <u>Batch Best Practices</u> (Document ID: 836362.1) available from <u>My Oracle Support</u>.

This facility will only operate if the **BATCH_RMI_PORT** is populated.

While the JMX client interface provided allows real time information to be displayed in a JMX browser, if a JMX browser is not used then the JMX interface may be interfaced using a command line utility. This utility is useful to allow third party products (such as batch schedulers) or other systems to control and monitor the state of the system.

This JMX batch command line allows the following to be performed:

- Identify what thread pools are defined in a threadpoolworker
- See what active batch processes or threads are currently running
- Be able to cancel a particular thread or a batch process
- Gracefully shutdown a threadpoolworker

To execute the command line, the administrator must:

- Logon to the machine running the ORMB application (any tier where the product software exists).
- Attach to the environment using the **splenviron.sh** command. This sets the appropriate environment settings for the script.
- Execute the JMX Batch command line utility:

Command Usage:

jmxbatchclient.sh –j [URL] [options]

Command Line Option	Description
-с	Specifies that active threads should be cancelled. Can be used with –f option to cancel only batch processes matching the regular expression provided. For example:
	Note: Cancelled threads are marked with the date, time, User ID, and IP address of the user who initiated the cancel command.
-d	Display the details of the currently active threads.
-f	If many threads are currently active, a filter can be supplied to only display or cancel threads that match the regex-based pattern.
	For example, the threadpool be filtered to show only the BAT1 with the option: -f.*BAT1.* as follows:
	jmxbatchclient.sh -j service:jmx:rmi:///jndi/rmi://myserver:9999/oracle/ouaf/batchConnect or -f .*BAT1.*
	Would yield:
	Options: -j service:jmx:rmi:///jndi/rmi://myserver:9999/oracle/ouaf/batchConnect or -f .*BAT1.*
	Connecting to service:jmx:rmi:///jndi/rmi://myserver:9999/oracle/ouaf/batchConnect or
	ActiveGridNode
	threadPools=[MYSERVER:5, LOCAL_THREAD_POOL:b9835d11f15fd71b:681ba91d:1200151a3c8:- 8000:0, SCHEDULER_DAEMON_THREAD_POOL:1] BatchThread_ZZQABAT1_1_of_1.31
-h	Display the available options and their descriptions.
-j	JMX URL to perform the action against (Required).

Command Line Option	Description
	This should match the spl.runtime.management.connector.url.default property specified in the threadpoolworker.properties.
-k	Specifying this option will result in the cancellation of all currently running threads and the stoppage of the threadpoolworker process.
	Note: Active threads within a cancelled threadpoolworker are marked with the date, time, User ID, and IP address of the user who initiated the kill command
-1	By default, all logging information is displayed and logged using log4j2. Supplying this option will result in only select information being displayed to the system output.
-s	Display the summary of the currently active threads is a listing format.
-t <wait></wait>	Amount of time, in ms, to wait as expressed in <wait> for active jobs to cancel.</wait>
-z	Display the cache details. Must be used in conjunction with -j option.

3.1.11 ouafDatabasePatch.sh - Install Database Patches

Points to Note:

The splenviron.sh utility must be executed before this utility can be used. See <u>splenviron - Set Environment Variables</u> for details.

For more information about patching refer to the <u>Software Configuration Management Series</u> (Document ID: 560401.1) available from <u>My Oracle Support</u>.

The ouafDatabasePatch allows database patches to be installed from the command line or via the Application Management Pack for Oracle Utilities. This utility is a companion to with <u>installSFGroup</u> (see <u>installSFGroup.sh - Install Software Patches</u>) which installs the software component of patches.

Command Usage:

ouafDatabasePatch.sh [-h] [-u] [-v] [-x] [-t toolsdir] [-p ouafparms]

Command Line Option	Description
-h	Show usage for patch.
-u	Show usage of command
-v	Display version of patch
-x	Database Password for applying patch
-b	Location of tools bin directory
-р	Additional parameters passed to utility (as per patch documentation).

Command Line Option	Description
	This must be the last parameter on the command line. This is primarily used by the Application Management Pack for Oracle Utilities.

3.1.12 PatchDeployUtility.sh - Create and Deploy Patch Rollups

Points to Note:

The splenviron.sh utility must be executed before this utility can be used. See <u>splenviron - Set Environment</u> Variables for details.

For more information about patching refer to the <u>Software Configuration Management Series</u> (Document ID: 560401.1) available from <u>My Oracle Support</u>.

The PatchDeployUtility allows prerequisite product software and database patches to be analyzed, downloaded, and applied in a single installation. This utility can be used from the command line or through the Application Management Pack for Oracle Utilities.

There are three phases for the utility to execute:

- **Report Mode** Generate a patch dependency list for a particular patch.
- **Download Mode** Download the patches not already downloaded from the Report mode list.
- **Rollup Mode** Create a single installer to install all the patches in the patch dependency list in one install.

Note: This utility does not install the patches. They must be installed using the **installSFgroup** and **ouafDatabasePatch** utilities.

Command Usage:

PatchDeployUtility.sh -f patchfile -m mode -l missingfile -d dir -r dir -n missingfile

Command Line Option	Description
-f patchfile	The full path and file name to the patchdependency.txt file of the patch to use as a reference point. This parameter is used by the REPORT mode only and is required for that mode.
-m mode	Mode. Supported values: REPORT, DOWNLOAD or ROLLUP.
-l missingfile	Full path and file name for output for REPORT mode. This file will contain the list of fixes that have not been downloaded. This parameter is used by the REPORT mode only and is required for that mode.
-d dir	Full path to location where any missing patches will be downloaded to when using the DOWNLOAD mode. This is also used by the ROLLUP mode as a source directory.
-r dir	Fill to location where the rollup files will be generated. This is the location used by the <u>installSFGroup</u> (see <u>installSFGroup.sh</u> - <u>Install Software</u> Patches) and <u>ouafDatabasePatch</u> (see <u>ouafDatabasePatch.sh</u> - <u>Install</u>

Command Line Option	Description
	<u>Database Patches</u>) utilities will be executed from. This parameter is by the ROLLUP mode only and is required for that mode.
-n missingfile	Full patch and file name of the missing patches generated by the REPORT mode. This parameter is used by DOWNLOAD and ROLLUP modes.

For example:

PatchDeployUtility.sh -f /scratch/mypatches/fix10001/data/etc/patchdependency.txt -m REPORT -l /scratch/patches/missing.txt

PatchDeployUtility.sh -n /scratch/patches/missing.txt -m DOWNLOAD -d /scratch/mypatches PatchDeployUtility.sh -n /scratch/patches/missing.txt -m ROLLUP -d /scratch/mypatches -r /scratch/myrollups

3.1.13 showjavaproc.sh - Show Java Processes

Points to Note:

The splenviron.sh utility must be executed before this utility can be used. See <u>splenviron - Set Environment</u> <u>Variables</u> for details.

This utility is mainly useful for embedded installations. It can be used for native installations, but the environment name will not be rendered.

The showjavaproc.sh utility lists the process ids for the Oracle WebLogic servers installed on the machine.

Command Usage:

showjavaproc.sh [-e envname] [-q]

Where:

Command Line Option	Description
blank	Find all the Oracle WebLogic servers running on the machine
-e envname	Filter the output by environment name. If it is found, then output a 1 return code
-q	Do not put output on screen. Useful for custom scripting.

For example:

showjavaproc.sh -e MYENVIRON || echo "Weblogic Java Process is running" showjavaproc.sh -e MYENVIRON && echo "Weblogic Java Process is NOT running"

3.1.14 splenviron – Set Environment Variables

Note: On the Linux/UNIX environment this utility creates a subshell upon completion.

The splenviron.sh utility initializes a defined set of environment variables and paths for an environment. This script must be run before any other script or utility is run within the environment.

Command Usage:

splenviron.sh -e <environment> [-c <command>] [-q] [-h]

Where:

Command Line Option	Description
-e <environment></environment>	<environment> is the environment id as installed in the cistab file.</environment>
-c <command/>	Execute <command/> after running splenviron.sh Command must be enclosed in double quotes (""). Default is shell (e.g. ksh).
-d	Quiet Mode. Do not show output from command. Any output from the –c command will be shown.
-h	Show usage.

Samples:

splenviron.sh –e DEMO splenviron –e DEV splenviron.sh –e DEMO –c "cat file.lst"

The splenviron.sh utility is executed whenever an environment needs to be initialized. One of the options to this script allows system administrators to optionally include the execution of an additional command as part of the environment initialization. This enables the system administrator to tune the environment shell more finely so they can change such settings as TimeZone, PATH or environment variables.

3.1.14.1 Extending the splenviron Command

If your implementation needs to add environment variables (or modify existing variables) for a third-party product you may wish to integrate with that product. For example, you might want to add some custom Java classes from a component that you want to use with the product.

When you run the **splenviron.sh** utility it sets the environment variables for the environment. These are standard variables as well as any required for operation of the product. For example, there are variables that can be used in utilities so they can be used across environments.

These environment variables can be extended (or added to) using one of the following options:

- Change to ALL environments on machine If your integration is common across all environments then you can set or alter environment variables using the following technique:
 - Create a script in a central location on the machine that sets or alters the appropriate environment variables. Ensure that the product administrator User ID has read/execute access to the location and the script.

- Set the CMENV environment variable with the location and name of the script to execute prior to running the splenviron.sh utility (for example, in your logon profile).
- When the splenviron.sh utility is run it will detect the script specified in the CMENV environment variable and execute the script to set or alter the environment variables.
- Change to a specific environment on machine If your integration is specific to an environment (or different for each environment, for example if you have a development as well as a test copy of the third-party product) then you can set or alter environment variables using the following technique:
 - Create a script called cmenv.sh in scripts subdirectory of the environment (usually \$SPLEBASE/scripts). Ensure the permissions are set appropriately for the product administration account to execute the script.
 - When the splenviron.sh utility is run it will detect the cmenv.sh script (or cmenv.cmd on Windows) and execute the script to set or alter the environment variables at the end of the splenviron.sh utility.
- Combination of both previously outlined options It is possible to combine the techniques in a combination which can mean you can have maximum flexibility. If you follow the instruction of both techniques, then the following will happen in the following order:
 - When the splenviron.sh utility is run it will detect the script specified in the CMENV environment variable and execute the script to set or alter the environment variables.
 - If there is a cmenv.sh script in the scripts subdirectory of the environment, it will execute
 the script to set or alter the environment variables. This may override, add, or alter
 environment variables already set.

In using this override technique, remember:

- If you alter any pre-existing environment variables, then ensure your changes are not going to circumvent product requirements. For example, do not alter paths used by the product.
- If you add files or directories to library variables or CLASSPATH ensure your changes are suffixed
 at the end of the variable. This is especially important for java classes as classes you use may
 conflict with product supplied ones; adding them at the end of the CLASSPATH will minimize the
 effects of conflicts.
- Do not remove any environment variables used by the product.

3.1.15 starttpw.sh - Start Threadpoolworker

Points to Note:

The splenviron.sh utility must be executed before this utility can be used. See <u>splenviron - Set Environment</u> Variables for details.

This utility is useful for developers.

This utility is a wrapper utility that calls the threadpoolworker script for use in command line batch submitters or from the command line.

Command Usage:

starttpw.sh [-h] [-Q] [threadpoolworker options]

Where:

Command Line Option	Description	
blank	Execute the [threadpoolworker options] in the background (nohup).	
-h	Show usage.	
-Q	Execute the [threadpoolworker options] in the foreground	

3.1.16 submitbatchREST.sh - Submit Batch Threads through the REST API

Points to Note:

The splenviron.sh utility must be executed before this utility can be used. See <u>splenviron - Set Environment</u> <u>Variables</u> for details.

This script is recommended instead of using the legacy script submitjob.sh as the legacy script does not populate the batch job submission tables.

This script uses the product's REST service F1-SubmitJob, submit operation to submit a batch job for execution. The REST service creates an entry in the Batch Job Submission table, which is polled by the batch daemon to pick up and execute the job.

Batch job parameters are defaulted from the batch control, when a job is submitted using this script. So, only the parameter information that is not already defaulted from the batch control configuration needs to be provided as input to this script.

The following options can be specified when executing utility submitjob.sh:

Command Usage:

submitbatchREST.sh [-b][-r][-a][-n][-l][-s][-c][-t][-d][-f][-m][- p] [-e] [-q][-o][-x][-u][-i][-w]

Command Line Option	Description
-b <bath code=""></bath>	Batch control of the batch process to submit. When submitting a batch process, a batch code is always required. The parameters are defaulted from the batch control. Override parameters can be provided using the -x option. This is the only mandatory parameter for calling this script.
-r <batch number="" rerun=""></batch>	Previous rerun number of the batch that needs re-submission.
-α	Batch submission user. Defaults to the user used for login.
-n	Email ID to which notification should be sent on batch completion.
-1	Language to be used for batch process.
-5	Desired batch job execution start date time. Defaults to current date time.

Command Line Option	Description
-c	Number of threads to be used for running the batch. Defaults to the value from corresponding batch control.
-t	Batch thread number that needs re-submission.
-d	Batch business date in YYYY-MM-DD format. Defaults to current date.
-f	Maximum commit records to override commit interval. Defaults to 1.
-m	Maximum timeout in minutes, to override program's timeout.
-p	To trace the start of program for troubleshooting purposes. Defaults to false
-е	To trace exit of program for troubleshooting purposes. Defaults to false.
-q	To trace SQL executions for trouble shooting purposes.
-0	To trace standard out of background processes for troubleshooting purposes.
-x	Batch job extra parameters can be set as comma delimited list of parameter & value. Any parameter passed must already be defined on the batch control. Defaults to batch control configuration.
-u	Login details can be provided in the format UserID:Password. If not provided, environment variables SUBMITREST_USER and SUBMITREST_PWD must be set. • SUBMITREST_USER - username to be used for authentication. • SUBMITREST_PWD - plain text password to be used for
-i	authentication. Complete REST URI for batch job submission. If not provided, either the environment variables WEB_HOST, WEB_SSLPORT/WEB_PORT and WEB_CONTEXT_ROOT must be set (OR) SPLEBASE must be set to get the environment details WEB_WLHOST, WEB_WLSSLPORT/ WEB_WLPORT and WEB_CONTEXT_ROOT from ENVIRON.INI.
	 WEB_HOST - Hostname of the target environment. WEB_SSLPORT - Port number of the target environment, in cases where SSL is used. WEB_PORT - Port number of the target environment, in cases where SSL is not used. WEB_CONTEXT_ROOT - Root context of the target environment.

Command Line Option	Description
-w	Interval time in seconds, to wait between polling of batch job status. Default value is 10 seconds, which is also the minimum value that can be provided. Provide larger values for long running batches to save resource usage.

Points to Note:

Environment variables, if any, needs to be set using EXPORT command. These variables will not persist between server machine restarts/unsettings. So, they will need to be set again.

The script exits with success code on batch job's successful completion.

3.1.17 submitjob.sh - Submit Batch Threads (Legacy Method of Batch Submission)

Points to Note:

The splenviron.sh utility must be executed before this utility can be used. See <u>splenviron - Set Environment</u> <u>Variables</u> for details.

For more examples of usage of this command, refer to the <u>Batch Best Practices</u> (Document ID: 836362.1) available from <u>My Oracle Support</u>.

This utility is not available in Oracle Utilities SaaS Cloud implementations. The Oracle Utilities SaaS Cloud includes a REST based interface that serves as an alternative.

Using this facility will not record Submission Method or Submission User as it directly integrates with the Batch Architecture and does not use the Batch Daemon.

The following options can be specified when executing utility submitjob.sh:

Command Usage:

submitjob.sh [-B][-b][-c][-d][-e][-f][-g][-h][-i][-J][-l][-L][-m] [-n] [- p][-P][-Q][-R][-r][-s][-t][-u][-x][-X]

Command Line Option	Description
-b <batch code=""></batch>	Batch code of the batch process to submit. When submitting a batch process, a batch code is always required. Either this option or —P may be specified, not both.
	If this option is specified, submitjob will use the supplied batch code to look for a default properties file for that batch code (e.g., VAL-SA.properties or VAL-SA.properties.xml as discussed above) and use those properties if found.
-c <thread count=""></thread>	Concurrent number of threads in which to run the process.
-d <date></date>	Process / business date. Format is YYYY-MM-DD

Command Line Option	Description
-e <thin clustered></thin clustered>	Execution mode for this submission. If execution mode THIN is selected, the JVM will create a full application context and run the batch process inside the JVM – i.e., it will not be submitted to a thread pool for a worker JVM to pick up and run. This is analogous to running the batch process using the existing SPLBATCH.sh utility.
	THIN mode is for development purposes only. If CLUSTERED is selected, the batch process will be submitted to run in the specified distributed thread pool (option –p). It is also possible to have the submitter JVM be a worker JVM and run the batch process (like THIN mode, but in parallel threads). See option –L.
-f <record count=""></record>	Record commit frequency count.
-g <four switches="" y n=""></four>	Positional tracing switches: 1. Program entry 2. Program exit 3. SQL statements 4. General program debugging info For example, NNYN will trace all SQL statements. Value of NNNN disables all tracing.
-h	Show help information. Display the available options and their descriptions. The information is not logged.
-i <rmi number="" port=""></rmi>	Port number of RMI Registry to start and/or reference. If specified with -R, this number will be used only to substitute applicable URL {port} references. This option will not add any new RMI/JMX properties - it can only be used to override existing ones.
-J	Do not start JMX connector. This option disables JMX monitoring for this JVM. As far as submitjob is concerned, options —i, —R and — J are only applicable to batch processes submitted in THIN mode, or CLUSTERED mode to the LOCAL thread pool. For each property prefixed by spl.runtime.management.connector.url that is defined with the default set of properties (e.g., in the submitbatch.properties file), the framework will start a JMX Connector for the specified URL. This activates JMX monitoring inside the worker node so that a client JMX console can be used to monitor and manage active threads. If this option is specified, the framework will not start any JMX connectors.
-I <eng fra etc.></eng fra etc.>	Language code. Relevant language pack must be installed.

Command Line Option	Description
-L	Submit this batch to the LOCAL thread pool (i.e. this JVM). Only applicable for CLUSTERED mode. If specified, any default thread pool property is ignored. This option and -p are mutually exclusive.
	By specifying option —L, the batch process is submitted to the LOCAL thread pool that every submitter JVM offers by default. This option is only applicable in a CLUSTERED mode execution (—e). This is like submitting the batch process in THIN mode (i.e., a worker JVM is not needed to run the batch process), except thread pool LOCAL can run multiple batch threads concurrently. For example, the following command will run batch process VAL—SA inside this submitter JVM (LOCAL thread pool) in 8 threads concurrently: submitjob.sh —b VAL—SA—c 8—L—e CLUSTERED
-n <email address=""></email>	Send a notification email when a batch process has ended to <email address="">. See Sending emails at the conclusion of batch process for more information.</email>
-p <threadpool name=""></threadpool>	Distributed thread pool in which to run the batch process. This option and -L are mutually exclusive.
-P	Issue console prompts for the standard batch process parameters. When submitting a batch process, a batch code is always required. Either this option or —b may be specified, not both. If — P is specified, the submitter JVM will prompt for the batch code and other run parameters. If a batch-specific properties file exists for the batch code entered at the prompt, it will NOT be used; the only defaults in effect would be the ones specified in submitbatch.properties.
-Q	Preview the properties that would be in use for the run without running the application. Specify other options along with this option to show how they would override or substitute the default properties. The information is not logged.
-R	Do not start a local RMI registry. As far as submitjob is concerned, options —i, —R and — J are only applicable to batch processes submitted in THIN mode, or CLUSTERED mode to the LOCAL thread pool. If property spl.runtime.management.rmi.port is defined as a default property (e.g., in the submitbatch.properties file), the batch framework will attempt to start an RMI registry on the given port number. This option can be used to suppress the automatic RMI registry startup. It may be required if an externally started RMI registry is already running. Note that if this option is used, the RMI port number supplied through the —i option is only used for substitution in the JMX Connector URLs.

Command Line Option	Description
-r <run number=""></run>	Run number of batch process to rerun.
-s <space name=""></space>	Space name for hard partition of workers. Default is MAIN. Used for development only.
-t <thread number=""></thread>	Number of individual threads for this submission. Specify O to automatically submit all threads.
-u <user id=""></user>	Application User ID used for batch process
-x <name=value,name=value,></name=value,name=value,>	Name=value pairs of INDIVIDUAL soft parameters expected by the batch program. Value portion may be enclosed in quotes. These parameters will be merged with any existing (defaulted) soft parameters. This option and -X are mutually exclusive.
-X <name=value,name=value,></name=value,name=value,>	Name=value pairs of ALL soft parameters expected by the batch program. Value portion may be enclosed in quotes. These parameters will replace all existing (defaulted) soft parameters. This option and -X are mutually exclusive.
-z <jumoptions></jumoptions>	Java options to use for submitter.

This utility returns two return codes:

- Zero (0) The job or thread was successful.
- Non-Zero The job or thread was NOT successful.

3.1.18 threadpoolworker.sh - Manage Threadpools

Points to Note:

The **splenviron.sh** utility must be executed before this utility can be used. See <u>splenviron - Set</u> Environment Variables for details.

For more examples of usage of this command refer to the <u>Batch Best Practices</u> (Document ID: 836362.1) available from <u>My Oracle Support</u>.

The following options can be specified when executing script threadpoolworker.

Command Usage:

threadpoolworker.sh [-d] [-e][-h][-i][-J][-p][-Q][-R][-s]

Where:

Command Line Options	Description
-d <y n></y n>	Whether the node is acting as a scheduler daemon.
	Specify N for No and Y for Yes. If you are already using a scheduler daemon in the online system or are not using online submission, then set this to N . Default is N .
-e <thiniclustered></thiniclustered>	Execution mode for this threadpool. If CLUSTERED is the threadpool will join the cluster specified in the threadpoolworker.properties file.

Command Line Options	Description
-h	Show command line help. List the available options and their descriptions. It is formatted for a 121-column width display. The information is not logged.
-i <rmi port=""></rmi>	Override port number for JMX. If specified with -R, this number will be used only to substitute applicable URL {port} references. This option will not add any new RMI/JMX properties - it can only be used to override existing ones. This option specifies the port number to: • Use when the framework starts an RMI Registry and • Substitute in all JMX Connector URL {port} references.
-J	Do not start JMX monitoring. For each property prefixed by spl.runtime.management.connector.url that is defined with the default set of properties (e.g., in the threadpoolworker.properties file), the framework will start a JMX Connector for the specified URL. This activates JMX monitoring inside the worker node so that a client JMX console can be used to monitor and manage active threads. If this option is specified, the framework will not start any JMX connectors.
-l2 <read_only read_writ E OFF></read_only read_writ 	Enable or disable batch caching. Default: READ_WRITE, OFF and READ_ONLY are reserved for specific processes. The value of OFF is used for selected utilities such as Configuration Migration Assistant and deployment utilities.
-p <name=value,name=value, ></name=value,name=value, 	Thread pool(s) offered by this worker node. Consists of one or more name=value pairs, where "name" is the name of the pool and "value" the number of threads offered in the pool. For example, DEFAULT=5,ONLINE=3
-Q	Preview the properties that would be active for this run. Used for testing. Preview the properties that would be in use for the run without running the application. Specify other options along with this option to show how they would merge with, override, or substitute the default properties. The information is not logged.
-R	Do not start a local RMI registry. If property spl.runtime.management.rmi.port is defined as a default property (e.g., in the threadpoolworker.properties file), the batch framework will attempt to start an RMI registry on the given port number. This option can be used to suppress the automatic RMI registry startup. It may be required if an externally started RMI registry is already running.
	Note: If this option is used, the RMI port number supplied through the –i option is only used for substitution in the JMX Connector URLs.
-s <space name=""></space>	Space name for "hard partition" of workers. Default is MAIN. Reserved for internal use only.

Command Line Options	Description	
-sf <file-path></file-path>	Generate or append command to a script. Reserved for system use.	
-s1 e to add to script>	Add line to script reference. Reserved for system use.	
-z <jum options=""></jum>	Add or override JVM options for threadpool.	

When threadpoolworker.sh is invoked, the command-line options will alter its default configuration. The default configuration options come from either internal system defaults or the threadpoolworker.properties file described above.

The properties are overridden in the following order:

- 1. The threadpoolworker.properties supersedes the internal system defaults.
- 2. The command-line options supersede the defaults in **threadpoolworker.properties** and the internal system defaults.

Example 1:

Assuming we have the above set of properties in **threadpoolworker.properties** and script **threadpoolworker.sh** is invoked as follows:

threadpoolworker.sh -d Y

This will replace the default "daemon" property to "N" (i.e., false) so that the properties now look as follows:

com.splwg.grid.distThreadPool.threads.DEFAULT=5 com.splwg.grid.distThreadPool.threads.LOCAL=0 com.splwg.batch.scheduler.daemon=false spl.runtime.management.rmi.port=9999

spl.runtime.management.connector.url.default=service:jmx:rmi:///jndi/rmi://{host}:{port}/oracle/ouaf/batchConnector

3.2 Starting and Stopping Using Consoles

In the native mode installation, there are several ways to start and stop your application:

 Log into the Oracle WebLogic Administration console for the domain and navigate to the server section where the product is installed. Using the Control function, start or stop the servers as necessary.

Note: This facility also allows enabling or disabling Administration Mode for a server. This allows administration tasks on that server while disabling end user access.

- For customers using Oracle Enterprise Manager, log into the Oracle Enterprise Manager console the product can be started and stopped using the following target types:
 - WebLogic Domain
 - WebLogic Server for product servers
 - Domain Application Deployment

Note: Refer to the <u>Oracle WebLogic Console Operations</u> section for starting and stopping information.

- For customers using the Oracle Application Management Pack for Oracle Utilities the product can be started and stopped using the following target types:
 - o Oracle Utilities Environment Starts and Stops all child targets in a single operation.
 - o Oracle Utilities Web Application
 - Oracle Utilities Web Services
 - Oracle Utilities Batch Server

Note: Refer to the <u>Operations from Oracle Enterprise Manager</u> section for information on operations from OEM.

4. Monitoring

This section outlines some basic monitoring regimes and methods for Oracle Utilities Application Framework applications. It is highly recommended that you read the <u>Performance Troubleshooting Guides</u> for Oracle Utilities Framework Based Products (Document ID: 560382.1) on My Oracle Support.

During monitoring you are typically looking for unusual activity and seeing if the current configuration of the product can handle the peaks and troughs of usage.

Unusual activity is an activity that is not a representative of the normal activity. For example, maybe during a marketing campaign the call center traffic doubles. This would be regarded as an unusual activity. At this point the current configuration may not be configured to handle the traffic, so the problem needs to be identified and the configuration changed to cater for the new load.

Also, during normal operations underlying problems may surface in the form of long running transactions, increases in error rates (in logs and timeouts) or runaway transactions. Runaway transactions are transactions that seem to be looping. These can be caused by data inconsistencies or bugs. Most of them are due to an unusual combination of data entries.

Some customers collect usage information to identity and analyze unusual activity. This is known as Site Profiling, Capacity Planning or Availability Planning. This is typically Proactive activity.

Oracle Utilities Application Framework stores usage information within the database that can be extracted for this purpose. This section outlines the methods and techniques you can use to extract this information reactively and proactively.

4.1 Monitoring Regimes

Typically, the art of monitoring is the collection and analysis of various pieces of information and then making changes to the configuration to address any issues or problems that occur.

With the various monitoring facilities available in your application, a combination that is valid for the site becomes a monitoring regime for that site. Typically, monitoring regimes pick up trends in the business or traffic volumes that require changes to the configuration. As part of the implementation of the product the monitoring regime for your site should be determined.

Typically, the monitoring regimes that are chosen, fall into several categories:

- Reactive Monitoring for any exception after it happens and making changes to the configuration
 to prevent the exception from occurring again. This is the most common regime adopted by IT
 groups. The only problem with this approach is that you have to experience potentially
 threatening outages before stabilization happens.
- Proactive Setting monitoring tolerances so that exception conditions are recognized before they
 happen and making configuration changes to prevent them from happening. This is also known as
 Problem Anticipation or Problem Prevention. This is the goal of most of the IT groups to ensure
 high availability.
- **Mixed** This is a mixture of pro-active and re-active regime. This is not uncommon.

4.2 Monitoring Client Machines

The product's front end is the Microsoft Internet Explorer browser. It is recommended to use the Internet Explorer browser, or any operating system monitoring specified by Microsoft to yield performance information from the client.

While collecting this information can be performed using various tools, it is usually not applicable in all monitoring situations unless the client machine is below the specification outlined in the *Oracle Revenue Management and Billing Installation Guide* for the platform and version of the product you are using. The browser collection points specified here are typically the ones that are better tailored for Oracle Utilities Application Framework's client.

Refer to the Microsoft documentation on how to fully monitor a client machine for performance information.

4.2.1 Monitoring the Desktop

One of the areas that customers tend to monitor is the desktop client. Typically, this involves using tools provided by Microsoft (and other vendors) to collect typical statistics, such as CPU, disk activity, memory usage and network usage. It is possible to monitor the client using the following tools:

- Desktop Vendor Tools (Performance Monitor) The Performance Monitor (located in the Administration Tools menu from Windows) is a starting point for monitoring the client. Refer to the Microsoft documentation on what aspects of a client machine to monitor.
- Network Monitor (netMon or other) Microsoft Windows Server includes a network capture facility that is handy to locate problems on a client machine. Alternatives, such as Ethereal, are available.
- **Network Latency** Network tools like **ping** and **traceroute** measure latency by determining the time it takes a given network packet to travel from source to destination and back, the so-called round-trip time. Round-trip time is not the only way to specify latency, but it is the most common. Inconsistent ping times or long ping times can indicate network issues.
- **Bandwidth Saturation levels** Several tools exist for computer networkers to measure the bandwidth of network connections. On LANs, these tools include netperf and ttcp.
- Packet Loss Packet loss is when data packets appear to be transmitted correctly at one end of a connection, but never arrive at the other. This might be because:
 - Network conditions are poor, and the packet became damaged in transit.
 - The packet was deliberately dropped at a router because of congestion.
 - Packet loss can be detected from the client PC using netstat and calculating the percentage of the Segments Sent that become Segments Retransmitted.

Note: *ping* and *traceroute* also include packet loss statistics.

Failed Connection Attempts - When the client and/or server cannot accept a connection, this
generates a Failed Connection Attempt on either the client or the server (or both). A large number
of Failed Connection Attempts can indicate networking or capacity issues on the client or server.
The most common cause is that the accept queue on the network parameters (usually on the
network cards) is full, and there are some requests waiting on the sync queue (usually on the
network card).

4.2.2 Client Debug Facility

Before a problem is to be registered with Oracle Support, the transaction that caused the problem should be traced to help support solve the issue quickly. A debug facility is provided within your application to help capture this additional information.

Logging of debug information can be set at a global level or at a local level. The global debug setting is not recommended for a production system as it reduces overall performance and therefore is not covered in this document.

The local level enables you to navigate to the problem area and then to switch debugging on for that individual user to recreate the problem. You can then collate the debug information to be sent to support.

To use this facility, you must specify an additional parameter at the end of the URL. For example:

http://<host>:<port>/<server>/cis.jsp?debug=true

Where,

Command Line Option	Description	
<host></host>	Web Application Server hostname	
<port></port>	Port allocated to product installation	
<server></server>	Context for the product at installation time	

Note: For the user to have debug access their User ID must have "Change" access to service F1DEBUG.

After the debug control menu is displayed, you navigate to the screen where the problem is encountered and then enable *Global Debug* by *toggling* the checkbox on. To turn off *Global Debug*, *toggle* the check box off. It is recommended to select *Trace All* for effective tracing. The other options are used by developers only. The trace information is written to the **spl*.log** in the \$SPLSYSTEMLOGS.

Note: The product uses spl_web-user.log and spl_service-user.log but spl_service-user.log may or may not appear depending on the installation type, therefore the name spl*.log is used.

All the logs displayed under this feature pertain to business/user logs. No technical logs would be displayed.

Debug allows specific information to be logged:

- Client Data Data presented to the browser. This pops up an additional window displaying the
 object as it is built.
- **Server Data** Data presented to the server. This pops up an additional window displaying the object as it is received by the server.
- Trace time Include time tracing in the log.

- Trace All Enable all trace modes below except Trace SQL Parameters.
- Trace Output Dump output from all calls
- Trace SQL Dump SQL statements
- Trace SQL Parameters Dump all result sets

Warning! This is not recommended for production systems as it will result in performance degradation.

- Program Start Write a record for every module start
- Program End Write a record for every module end

Most tracing in non-development uses Trace All unless otherwise instructed by Oracle Support. All debug information is written to the spl*.log files.

4.2.2.1 Steps to Using the Debug Facility

To use the debug facility, you follow the process:

 Add ?debug=true to the URL for your application. This will display the debug icon on the browser screen as shown below:



Figure 6: Debug Toolbar

Click on the debug icon to display the debug toolbar.




Figure 7: Debug Toolbar

- Start Debug Start the logging of the transaction.
- Stop Debug Stop the logging process.
- Show Trace Show trace information (configuration-based objects only).
- Clear Trace Clear trace Information.
- Show User Log Show debug information for the user (line limit is configurable).
- Show Log Show logs for all users (applicable for administrator). Can be selected from the Show User Log drop-down.
- o Global Debug Set debug level.

Select Global Debug to specify the level of debug information. This will display the Debug Control
window where you should ensure that Trace All is selected. Other options should only be used if
instructed by Oracle Support. A sample of the Debug Control dialog is shown below:




Figure 8: Debug Controls

- Navigate to the transaction that you wish to trace as a user would normally operate. Press Start
 Debug to initiate debug.
- Run the transaction that you want to trace and to recreate the issue. While you work the trace information is written to the log files.
- Deselect Global Debug or press Stop Debug so that debugging is disabled. This will stop debug
 code from writing to the log. If you select Show User Log the log lines output by the debug facility
 are displayed (up to the line limit specified). This will only show lines applicable to the Current User
 only.

Note: If the User ID is shared across multiple physical users, then the information may contain debug information from multiple sessions.

4.3 Monitoring Web/Business Application Server

There are several methods that are available for monitoring a Web Application from a JEE web application server:

- Java Management Extensions (JMX) Most web application servers expose JMX Management
 Beans (MBeans) to allow JMX browsers to view and use this information. Java 7 has a predefined
 set of MBeans that can be enabled automatically.
- Web Application Server Console All web application servers offer a web-based console that
 provides both administration and basic monitoring functions. These are usually sufficient for spot
 real time checking of tolerances and basic monitoring. Some console use calls to JMX APIs
 provided by the web application server vendor and built into Java 7 (and above).
- Oracle Enterprise Manager Customers using Oracle WebLogic can use the Fusion Middleware targets available within Oracle Enterprise Manager to monitor online and web services applications. Customers using Application Management Pack for Oracle Utilities can use monitoring capabilities of those targets as well.

- Command Based Utilities Apart from the console, most web application server vendors offer a
 command line utility to extract performance information (or perform administration). Most
 console utilities call JMX MBeans and provide a command line interface into JMX that can be used
 natively.
- **Log-based Monitoring** Most web application servers provide standardized logs that can be analyzed using consoles, log monitors or simple scripts.
- Native OS Utilities Most operating systems are becoming Java aware and provide OS and Java monitoring from OS monitoring facilities.

Refer to the <u>Performance Troubleshooting Guides for Oracle Utilities Framework Based Products</u> (Document ID: 560382.1) on <u>My Oracle Support</u> for details on the monitoring aspects of your application.

4.4 JMX Based Monitoring

With the advent of <u>Java Management Extensions</u> (JMX) technology into base java, it is possible to use the technology to monitor and manage java infrastructure from a <u>JSR160</u> compliant JMX compliant console (or JMX browser). Whilst the JEE components of the product can use basic JMX statistics such as Memory usage, Threads, Class information and VM summary information, there are application specific JMX classes added to the product to allow greater levels of information to be display and additional operations.

The Oracle Utilities Application Framework has implemented a set of product specific JMX classes on the web application server and business application server tiers of the architecture to allow the following:

- Management of the cache of the web application server. See <u>Server Cache</u> for more details of this cache.
- Collection of JVM information and performance statistics for memory, thread usage and operating system level information. Most of these are extensions of java.lang.management classes.
- Collection of service-based performance information for SLA tracking on the business application server.

To use this facility the facility must be configured and enabled to allow the collection of the relevant information. This can be done at installation time by using the following configuration settings:

Configuration Setting	Deployment Details
WEB_JMX_RMI_PORT_PERFORMANCE	Port Number used for JMX based management for web application server.
ouaf.jmx.splwlsg.base.support.management.m bean.JVMInfo	Globally enable or disable JVMInfo Mbean (setting in spl.properties). Default is enabled.
ouaf.jmx.com.splwg.base.web.mbeans.FlushBe an	Globally enable or disable FlushBean Mbean (setting in spl.properties). Default is enabled.
ouaf.jmx.com.oracle.ouaf.uws.mbeans.WSFlus hBean	Globally enable or disable WSFlushBean Mbean (setting in spl.properties). Default is enabled.
BSN_JMX_RMI_PORT_PERFORMANCE	Port Number used for JMX based management for Business Application Server.

Configuration Setting	Deployment Details
ouaf.jmx.com.splwg.ejb.service.management. PerformanceStatistics	Globally enable or disable PerformanceStatistics Mbean (setting in spl.properties). Default is enabled.
BSN_JMX_SYSUSER	Default JMX User ID for both web application server and business application server.
BSN_IMX_SYSPASS	Default JMX Password for both web application server and business application server.
BATCH_RMI_PORT	Port Number used for JMX based management for background processing.
WEB_BATCH_CLUSTER_URL	Cluster URL override to be used for JMX based management for background processing. This can manually be set to identify an administration node for processing.

These settings are registered in the <u>ENVIRON.INI</u> (see <u>ENVIRON.INI - Environment Configuration File</u>) for setting in the relevant configuration files. It is important that the values used for these port numbers are unique across all environments within a machine. The security used for these ports are defined as outlined in the <u>JMX Security</u>.

4.4.1 Web Application Server JMX Reference

Once configured a JMX client (for example, jconsole) can be used to connect to the JMX information using the following Remote Connection string:

 $service:jmx:rmi:///jndi/rmi://<host>:<jmx_port>/orac1e/ouaf/webAppConnector$

and

service:jmx:rmi:///jndi/rmi://<host>:<jmx_port>/oracle/ouaf/iwsConnector

Where,

Command Line Option	Description
<host></host>	The web application server host name.
<jmx_port></jmx_port>	The JMX Port specified using WEB_JMX_RMI_PORT_PERFORMANCE for the online and WEB_JMX_RMI_PORT_PERFORMANCE inbound web services from the ENVIRON.INI (see ENVIRON.INI - Environment Configuration File) configuration file.

The credentials provided to the JMX console are as configured in <u>JMX Security</u>. Upon successful connection to the JMX port and host with the correct credentials provides access to the Mbean information. The figure below illustrates the successful connection to the JMX Mbeans using **jconsole** as an example:




Figure 9: Example Web Application Server Mbeans in jconsole

The structure of the Mbean is shown by the figure below:




Figure 10: Web Application Server Mbeans

The following table summarizes the Mbean attributes and operations for the web application server:

Mbean	Usage
BaseMasterBean	Master MBean
Attributes	
NumberOfMbeans	Returns number of active Mbeans
MBeanList	Returns an array with the list of Mbeans defined to this Master Mbean.
Operations	
disableMbean	Disables Mbean with designated name as a par
enableMbean	Enables Mbean with designated name
disableMbean	Returns a list with the list of Mbeans defined to this BaseMasterBean. Names can be programmatically used to supply parameters to disableMbean and enableMbean.
enableJVMSystemBeans	Enables base JVM system Mbeans
disableJVMSystemBeans	disables base JVM system Mbeans
FlushBean/WSFLushBean	Manages Online/IWS Cache
Attributes	
VersionInfo	Returns string of base version number of Mbean.
CompleteClassPath	Returns classpath name of Mbean.
Operations	
flushAll	Reset all elements in online data cache
flushDropDownCache	Resets cached elements of the online drop-down lists in online data cache
flushDropDownField	Resets drop down fields in online data cache (Development use only)
flushFieldAndFKMetaData	Resets Field and Foreign Key Meta Data in online data cache
flushMenu	Reset Menu items in online data cache
flushMessageCatalog	Reset field labels in online data cache
flushMessaging	Reset messages in online data cache
flushNavigationInfo	Reset navigation information in online data cache
flushPortalMetaInfo	Reset portal and zone information in online data cache
flushSystemLoginInfo	Reset security information in online data cache
flushUIXSLs	Reset user interface style sheets in online data cache.

Mbean	Usage
JVMInfo	JVM Information Mbean
Attributes	
CompleteClassPath	Displays the class path of the JVMInfo mbean.
Operations	
classPath	Returns the full classpath used by the online JVM
systemSettings	Returns the attributes of the JVM for debugging and support purposes.
JVMSystem	JVM Mbean (Java base metrics)
ClassLoadingMXBean	Class Loading JVM Mbean
Attributes	
LoadedClassCount	Returns the number of classes that are currently loaded in the JVM
ObjectName	The ObjectName for uniquely identifying the MXBean for the class loading system within an MBeanServer. In this case it is set to java.lang:type=ClassLoading
TotalLoadedClassCount	Returns the total number of classes that have been loaded since the JVM was last started.
UnloadedClassCount	Returns the total number of classes unloaded since the Java virtual machine has started execution.
Verbose	Enables or disables the verbose output for the class loading system. Default is false (disabled)
MemoryMXBean	Memory JVM Mbean
Attributes	
HeapMemoryUsage	Returns the current memory usage of the heap that is used for object allocation. Initial, Committed, Maximum and Used memory statistics are provided for Heap memory
NonHeapMemoryUsage	Returns the current memory usage of non-heap memory that is used by the JVM. Initial, Committed, Maximum and Used memory statistics are provided for non-heap memory
ObjectPendingFinalization	Returns the approximate number of objects for which finalization is pending (used for diagnosing memory leaks).
ObjectName	The ObjectName for uniquely identifying the MXBean for the memory system within an MBeanServer. In this case it is set to java.lang:type=Memory

Mbean	Usage
Verbose	Enables or disables the verbose output for the memory system. Default is false (disabled).
Operations	
gc	Initiate garbage collection
Notifications	
javax.management.Notification	Used for low memory notifications. Notification Types supported: java.management.memory.threshold.exceeded, java.management.memory.collection.threshold.exceeded
OperatingSystemMXBean	Operating System Mbean
Attributes	
MaxFileDescriptorCount	Returns the File Descriptor Maximum Limit in force on the JVM
OpenFileDescriptorCount	Returns the number of Open File Descriptors currently used by JVM
CommittedVirtualMemorySize	Returns the amount of committed virtual memory (that is, the amount of virtual memory guaranteed to be available to the running process).
FreePhysicalMemorySize	Returns the total amount of free physical memory
FreeSwapSpaceSize	Returns the total amount of free swap space
ProcessCpuTime	Returns the amount of process CPU time consumed by the JVM
TotalPhysicalMemorySize	Returns the total amount of physical memory
TotalSwapSpaceSize	Returns the total amount of swap space
Name	Returns the operating system name
Version	Returns the version of the operating system
Arch	Returns the operating system architecture
AvailableProcessors	Returns the number of available processors to the JVM
SystemLoadAverage	Returns the system load average for the last minute.
Name	Returns the name representing the running JVM. The returned name string can be any arbitrary string and a JVM implementation can choose to embed platform-specific useful information in the returned name string. Each running virtual machine could have a different name.
ClassPath	Returns the Java class path that is used by the system class loader to search for class files.

Mbean	Usage
ObjectName	The ObjectName for uniquely identifying the MXBean for the operating system within an MBeanServer. In this case it is set to java.lang:type= OperatingSystem
RuntimeMXBean	<u>Java Runtime</u> MBean
Attributes	
Starttime	Returns the start time of the Java virtual machine in milliseconds. This method returns the approximate time when the JVM started.
ManagementSpecVersion	Returns the version of the specification for the management interface implemented by the running JVM.
VmName	Returns the Java virtual machine implementation name.
VmVendor	Returns the Java virtual machine implementation vendor.
VmVersion	Returns the Java virtual machine implementation version.
SpecName	Returns the Java virtual machine specification name.
SpecVendor	Returns the Java virtual machine specification vendor.
SpecVersion	Returns the Java virtual machine specification version.
LibraryPath	Returns the Java library path
BootClassPath	Returns the boot class path that is used by the bootstrap class loader to search for class files.
Uptime	Returns the uptime of the Java virtual machine in milliseconds.
BootClassPathSupported	Tests if the JVM supports the boot class path mechanism used by the bootstrap class loader to search for class files. Returns false if not supported; true if supported.
InputArguments	Returns the input arguments passed to the JVM which does not include the arguments to the main method. This method returns an empty list if there is no input argument to the JVM. Typically, not all command-line options to the 'java' command are passed to the Java virtual machine. Thus, the returned input arguments may not include all command-line options.
SystemProperties	Returns a map of names and values of all system properties.
ThreadCount	Returns the current number of live threads including both daemon and non-daemon threads
PeakThreadCount	Returns the peak live thread count since the JVM started or peak was reset.

Mbean	Usage	
TotalStartedThreadCount	Returns the total number of threads created and also started since the JVM started.	
DaemonThreadCount	Returns the current number of live daemon threads.	
ThreadContentionMonitoringSupporte d	Tests if the JVM supports thread contention monitoring. Returns <i>false</i> if not supported; <i>true</i> if supported.	
ThreadContentionMonitoringEnabled	Enables or disables thread contention monitoring. Set to false to disable; true to enable.	
CurrentThreadCpuTime	Returns the total CPU time for the current thread in nanoseconds. The returned value is of nanoseconds precision but not necessarily nanoseconds accuracy. If the implementation distinguishes between user mode time and system mode time, the returned CPU time is the amount of time that the current thread has executed in user mode or system mode.	
CurrentThreadUserTime	Returns the CPU time that the current thread has executed in user mode in nanoseconds. The returned value is of nanoseconds precision but not necessarily nanoseconds accuracy.	
ThreadCpuTimeSupported	Tests if the JVM supports CPU time measurement for the current thread. Returns <i>false</i> if not supported; <i>true</i> if supported.	
ThreadCpuTimeEnabled	Enables or disables thread CPU time measurement. The default is platform dependent. Set to <i>false</i> to disable; true to <i>enable</i> .	
CurrentThreadCpuTimeSupported	Tests if the Java virtual machine supports CPU time measurement for the current thread. Returns <i>false</i> if not supported; <i>true</i> if supported.	
ObjectMonitorUsageSupported	Tests if the Java virtual machine supports monitoring of object monitor usage. Returns <i>false</i> if not supported; <i>true</i> if supported.	
Synchronizer Usage Supported	Tests if the JVM supports monitoring of ownable synchronizer usage. Returns <i>false</i> if not supported; <i>true</i> if supported.	
AllThreadlds	Returns all live thread IDs. Some threads included in the returned array may have been terminated when this method returns.	
ObjectName	The ObjectName for uniquely identifying the MXBean for the java runtime within an MBeanServer. In this case it is set to java.lang:type=Runtime	

Mbean	Usage
Operations	
dumpAllThreads	Returns the thread info for all live threads with stack trace and synchronization information. Some threads included in the returned array may have been terminated when this method returns. • Locked Monitors - if true, dump all locked monitors. • Locked Synchronizers - if true, dump all locked ownable synchronizers.
findDeadlockedThreads	Finds cycles of threads that are in deadlock waiting to acquire object monitors or ownable synchronizers. Threads are deadlocked in a cycle waiting for a lock of these two types if each thread owns one lock while trying to acquire another lock already held by another thread in the cycle.
getThreadCpuTime	Returns the total CPU time for a thread of the specified ID in nanoseconds. The returned value is of nanoseconds precision but not necessarily nanoseconds accuracy. If the implementation distinguishes between user mode time and system mode time, the returned CPU time is the amount of time that the thread has executed in user mode or system mode.
getThreadInfo	Returns the thread info for a thread of the specified id with no stack trace.
getThreadInfo	Returns the thread info for each thread whose ID is in the input array ids with no stack trace.
getThreadInfo	Returns thread information for a thread of the specified id, with stack trace of a specified number of stack trace elements. The <code>maxDepth</code> parameter indicates the maximum number of <code>StackTraceElements</code> to be retrieved from the stack trace. This method does not obtain the locked monitors and locked synchronizers of the thread.
getThreadInfo	Returns the thread information for each thread whose ID is in the input array ids, with stack trace of a specified number of stack trace elements. The maxDepth parameter indicates the maximum number of StackTraceElements to be retrieved from the stack trace. This method does not obtain the locked monitors and locked synchronizers of the threads.

Mbean	Usage	
getThreadInfo	Returns the thread info for each thread whose ID is in the input array ids, with stack trace and synchronization information.	
	This operation obtains a snapshot of the thread information for each thread including:	
	the entire stack trace,	
	 the object monitors currently locked by the thread if lockedMonitors is true, and 	
	the ownable synchronizers currently locked by the thread if <i>lockedSynchronizers</i> is true	
getThreadUserTime	Returns the CPU time that a thread of the specified ID has executed in user mode in nanoseconds.	
resetPeakThreadCount	Resets the peak thread count to the current number of live threads.	
OEMTargetsBean	Application Management Pack for Oracle Utilities interface	
Operations		
toXML	Generate Target information for Oracle Enterprise Manager. An XML document with information for the Application Management Pack for Oracle Utilities.	

4.4.2 Business Application Server JMX Reference

Once configured a JMX client (for example, jconsole) can be used to connect to the JMX information for the business application server using the following remote connection string:

service:jmx:rmi:///jndi/rmi://<host>:<jmx_port>/oracle/ouaf/ejbAppConnector

Where,

Command Line Option	Description
<host></host>	The business application server host name.
<jmx_port></jmx_port>	The JMX Port specified using BSN_JMX_RMI_PORT_PERFORMANCE from the <u>ENVIRON.INI</u> (see <u>ENVIRON.INI</u> - <u>Environment Configuration</u> <u>File</u>) configuration file.

The credentials provided to the JMX console are as configured in <u>JMX Security</u>. Upon successful connection to the JMX port and host with the correct credentials provides access to the Mbean information. The figure below illustrates the successful connection to the JMX Mbeans using **jconsole** as an example:




Figure 11: Business Application Server Mbeans in jconsole Example

The structure of the Mbean is shown in the figure below:




Figure 12: Business Application Server Mbeans

The following table outlines the Mbean attributes and operations for the business application server:

Mbean	Usage	
PerformanceMBeanController	Performance Mbean Controller	
Operations		
disableMbean	Disable PerformanceStatistics Mbean	
enableMbean	Enable PerformanceStatistics Mbean	
PerformanceStatistics	Performance Statistics	
Attributes		
ReadCount	Returns number of executed <i>read object</i> calls since last reset or last time collection enabled.	
DeleteCount	Returns number of executed <i>delete object</i> calls since last reset or last time collection enabled.	
ChangeCount	Returns number of executed <i>change object</i> calls since last reset or last time collection enabled.	
AddCount	Returns number of executed <i>add object</i> calls since last reset or last time collection enabled.	
DefaultItemCount	Returns number of executed calls to <i>default the object values</i> since last reset or last time collection enabled.	
ExecuteBOCount	Returns number of calls to <i>Business Objects</i> since last reset or last time collection enabled.	
ExecuteBSCount	Returns number of calls to <i>Business Services</i> since last reset or last time collection enabled.	
ExecuteListCount	Returns number of calls to <i>List based services</i> since last reset or last time collection enabled.	
ExecuteSearchCount	Returns number of calls to <i>search based services</i> since last reset or last time collection enabled.	
ReadSystemCount	Returns number of calls to <i>Oracle Utilities Application Framework</i> System Objects since last reset or last time collection enabled.	
ValidateCount	Returns number of calls to <i>Validate objects</i> since last reset or last time collection enabled.	
ExecuteSSCount	Returns number of calls to <i>Service Scripts</i> since last reset or last time collection enabled.	
Operations		
CompleteClassPath	Returns the class path used for the Mbeans.	
reset	Resets statistical values. See the <u>Resetting Statistics</u> section for more advice on this operation.	

Mbean	Usage	
maxTime	Returns maximum (worst case) time, in ms, for the designated service since the last reset or last time collection enabled.	
minTime	Returns minimum (best case) time, in ms, for the designated service since the last reset or last time collection enabled.	
completeExecutionDump	Returns complete statistics for all services executed since the last reset or last time collection enabled. See the Execution Dump Format section for details of format.	
avgTime	Returns average time, in ms, for the designated service since the last reset or last time collection enabled.	
executionInfo	Returns complete statistics for the designated service executed since the last reset or last time collection enabled. See the Execution Dump Format section for details of format.	
calledServices	Returns list of services and service types since the last reset or last time collection enabled. See the <u>Service Lists</u> section for details of format.	
ProbeTransactionMbean	Component Probe	
Operations		
checkApplicationServer	Constructs HTTP/HTTPS request and returns RFC 2616 HTTP response code and response time in ms.	
checkDatabaseConnectivity	Executes SQL SELECT to test database connectivity. Returns response time in ms.	
checkBusinessApplicatioServer	Executes base service (read only) to return application server performance in ms.	
OEMTargetsBean	Application Management Pack for Oracle Utilities Interface	
Operations		
toXML	Generate Target information for Oracle Enterprise Manager. An XML document with information for the Application Management Pack for Oracle Utilities.	

Note: The times quoted in the statistics only record times experienced from the business application server down to the data and back. They do not include network time to the web application server, any time spent by the web application server, network time to the browser client or browser rendering times. The business application server time represents the typical majority of the time spent in a transaction.

4.4.3 Batch JMX Reference

Once configured a JMX client (for example, jconsole) can be used to connect to the JMX information for the business application server using the following remote connection string:

service:jmx:rmi:///jndi/rmi://<host>:<jmx_port>/oracle/ouaf/batchConnector

Where:

Command Line Option	Description	
<host></host>	A Batch Server host name	
<jmx_port></jmx_port>	The JMX Port specified using BATCH_RMI_PORT from the ENVIRON.INI (see ENVIRON.INI - Environment Configuration File) configuration file.	

Note: In a multi-host environment, it is possible to reserve a specific host/port combination using the WEB_BATCH_CLUSTER_URL which specifies a specific host and BATCH_RMI_PORT combination as the administration machine.

The credentials provided to the JMX console are as configured in <u>JMX Security</u>. Upon successful connection to the JMX port and host with the correct credentials provides access to the Mbean information. The figure below illustrates the successful connection to the JMX Mbeans using **jconsole** as an example:




Figure 13: Batch Server Mbeans in jconsole Example




Figure 14: Batch Thread Mbean in jconsole Example

The structure of the Mbean is shown in the figure below:




Figure 15: Batch Server Mbeans

The following table outlines the Mbean attributes and operations for the business application server:

Mbean	Usage	
BatchCluster	Cluster Mbean for cluster with name <clustername></clustername>	
Attributes		
Address	Cluster address as specified in <u>COHERENCE CLUSTER ADDRESS</u> in <u>ENVIRON.INI</u>	
Name	Name of the Cluster as specified in <u>COHERENCE CLUSTER NAME</u> in <u>ENVIRON.INI</u>	
Port	Port number assigned to Cluster as specified in COHERENCE CLUSTER PORT in ENVIRON.INI	
ClusterAsString	XML representation of the cluster for use with Application Management Pack for Oracle Utilities. The structure represents the hierarchy of JMX calls in XML format.	
Operations		
flushAllCaches	Flush the data reuse cache across the batch cluster. Invoke this operation to reload configuration data changes for batch jobs.	
registerClusterMBeans	Register the Mbeans for lower-level tracking. This needs to be invoked to allow threadpool and batch thread level tracking.	
unregisterClusterMBeans	Disable lower-level tracking. This stops low level tracking.	
ThreadPools	Threadpool Statistics (an entry per threadpool) Note: This tree will only appear if registerClusterMbeans is executed to enable the additional metrics.	
Attributes		
Name	Name of Threadpool	
AvailableThreads	Number of spare threads for batch processes. A value of zero (0) indicates the threadpool is at capacity.	
	Note: For cache or administration threadpools, this value is always zero (0).	
NumberOfMembers	Number of members/hosts defined to the threadpool. A value of zero (0) indicates a cache or administration threadpool.	
Members	Member (submitters/nodes) Statistics	
Attributes		
Hostname	Name of Host hosting this threadpool instance	
JVMName	Name of JVM assigned at runtime	
PID	Unique OS Process ID for JVM	

Mbean	Usage	
Memberld	Member Number. This number of unique across the cluster and is used to track the member internally by the framework.	
Info	Parameters used to start threadpool instance in free format. This is primarily used by Application Management Pack for Oracle Utilities.	
Operations		
flushAllCaches	Flush the cache for this instance	
stopNode	Stop this member. This allows members to be stopped manually.	
displayClusterCache	Cluster Cache in free format. This is primarily used by Application Management Pack for Oracle Utilities.	
ClusterNode	Member information about the member you are connected to	
Attributes		
JVMName	Name of JVM assigned at runtime	
PID	Unique OS Process ID for JVM	
Info	Parameters used to start threadpool instance in free format. This is primarily used by Application Management Pack for Oracle Utilities.	
Operations		
flushAllCaches	Flush the cache for this instance	
stopNode	Stop this member. This allows members to be stopped manually.	
displayClusterCache	Cluster Cache in free format. This is primarily used by Application Management Pack for Oracle Utilities.	
BatchThread/BatchJob	Batch Thread/Job Metrics	
	Note: BatchThreads is spawned per thread. BatchJob is spawned for jobs with multiple threads as a control node. BatchJob will not be spawned for single thread jobs.	
Attributes		
BatchCd	Batch Code	
BatchNumber	Batch Number	
CancelRequested	True if the thread has been asked to stop running. See CancelRequestedBy.	
CancelRequestedBy	If CancelRequested=true, this will be a string indicating the workstation from where the cancellation was requested. This value will also be logged to the Batch Run Tree.	
DateTimeStarted	The date and time the batch process was started.	

Mbean	Usage	
DistThreadPool	The thread pool to which this batch process belongs.	
ElapsedTime	How long the batch process has been running in java format	
ExecutionStrategyClass	This indicates the commit strategy followed by the program	
JMXInfo	Additional Tags for batch thread	
LanguageCD	Language Code used for execution for messages	
MaxExecutionAttempts	MAX-ERROR value	
MaximumCommitRecords	Commit Interval for Timeouts (Legacy Support only)	
MaximumTimeoutMinutes	Timeout Interval (Legacy Support only)	
ProcessDate	Business Date	
ProgramName	The program name executed. This is set on the Batch Control.	
ProgramType	The program type; Value is typically: Java	
RecordsCommitted	The number of record updates that have been committed to the database. See note below.	
RecordsInError	The number of records so far in error. This is what will be logged to the Batch Run Tree. See note below.	
RecordsProcessed	The number of records processed so far. This is what will be logged to the Batch Run Tree. See note below.	
RerunNumber	Rerun Number if RunType is Rerun.	
RunType	The type of run: New Run, Restart or Rerun.	
SoftParameters	List of job parameters from Batch Control.	
Status	The current status of the thread. Valid values are: Initializing" (at the start of execution to the call to getJobWork in the application class); Getting Work means it is currently in the process of selecting the work units for the batch process; Got Work means it is has successfully selected the work and is in the process of initiating the threads.	
ThreadCount	Thread Limit	
ThreadNumber	Thread Number	
TraceProgramEnd	Whether tracing for Program End is enabled	
TraceProgramStart	Whether tracing for Program Start is enabled	
TraceSQL	Whether SQL statement tracing is enabled	
TraceStandardOut	Whether output tracing is enabled	
Userld	User used for authorization	

Mbean	Usage	
WorkUnitSize	The total number of work units for this batch process. For new and restarted runs, this will always contain the total number of work units as selected in the getJobWork method when the batch process was originally started.	
WorkUnitSizeThisRun	This is the number of work units for this run. For a restarted run, this value will typically be less than the above value; otherwise, they will be the same.	
WorkUnitsCommitted	The number of work units that have had their work committed.	
WorkUnitsInError	The work units that have been found to be in error so far.	
WorkUnitsProcessed	The work units that have been processed so far.	
Operations		
cancelThread	Cancel this thread. This updates CancelRequested and CancelRequestedBy. Information is persisted on the Batch Run Tree.	
OEMTargetsBean	Application Management Pack for Oracle Utilities Interface	
Operations		
toXML	Generate Target information for Oracle Enterprise Manager. An XML document with information for the Application Management Pack for Oracle Utilities.	

Points to Note:

Each batch thread is uniquely identifiable in the BatchThread JMX call with the name mbean.mbean.chatchcd.chatchcd is the batch control identifier for the job, thread. Where mbean is BatchJob or BatchThread is the batch control identifier for the job, thread_of_threadlimit and javathread is the internal java thread number.

The "Record..." numbers are what will be used to log to the Batch Run Tree, and they are usually in step with the "WorkUnit..." values. The reason they are shown separately is because it is possible for custom background processes manually manipulate the record counts for the Batch Run Tree. The true progress status of a thread is reflected in the "WorkUnit..." counts.

4.4.4 JMX Security

By default, when JMX is enabled for either the web application server, web service, or business application server then a default JMX configuration using simple security is implemented as outlined in http://java.sun.com/javase/6/docs/technotes/guides/management/agent.html.

The simple security system consists of two files that control the access permissions and passwords specified by default for the installation:

Configuration Setting	Location of file	Template
Password File	scripts/ouaf.jmx.password.file	ouaf.jmx.password.file.templ ate
Access Control File	scripts/ouaf.jmx.access.file	ouaf.jmx.access.file.template

These files are built by the initialSetup utility using the templates indicated. Refer to the templates or generated files for valid values. The format of these files is dictated by http://java.sun.com/javase/6/docs/technotes/guides/management/agent.html#gdeup.

Note: By default, the passwords stored in these files are in encrypted text. Alternative security schemes are allowed as documented in the link above. This will require custom templates (see Implementing Custom Templates) and changes to specific files to implement.

4.4.5 Extending JMX Security

Whilst the base installation of ORMB application uses the basic level of security there are ways of extending the current security setting:

- If the default security scheme is sufficient for your needs then additional users may be manually added using the user exits (see User Exit Include Files) for the above files.
- For production it is recommended to implement an SSL based solution as outlined in http://docs.oracle.com/javase/6/docs/technotes/guides/management/agent.html.

Refer to the *Oracle Revenue Management and Billing Security Guide* for more schemes available for this process.

4.4.6 Execution Dump Format

In previous versions (V1.x) of the Oracle Utilities Application Framework based products, it was possible to extract performance information from the business application server using a logging-based method using the Oracle Tuxedo txrpt utility. This facility was useful in tracking performance of individual services over time to detect non-compliance against Service Level Agreement targets. With the advent of later versions of the Oracle Utilities Application Framework, the need for Oracle Tuxedo was removed but there was a need for performance information to be collated.

In the latest version of the Oracle Utilities Application Framework, it is possible to track performance information using JMX to process externally to check performance and check compliance against Service Level Agreements.

To extract the information from ORMB application, the following needs to be done:

- Use a JMX browser (or JMX console) product to connect to the business application server JMX port using the appropriate credentials.
- Invoke the completeExecutionDump operation from the PerformanceStatistics Mbean. This will return a Comma separated values, with field names in the header record, containing the performance data which can be transferred to the clipboard (or whatever format supported by the JMX client). The format of the CSV is shown in the table below:

Column	Comment
ServiceName	Name of Service
ServiceType	Type Of Service or Action (see the <u>Service Lists</u> section for valid values)
MinTime	Minimum Service Time, in ms, since last reset
MaxTime	Maximum Service Time, in ms, since last reset
Avg Time	Average Service Time, in ms, since last reset
# of Calls	Number of Calls to Service since last reset
Latest Time	The service time of the latest call, in ms
Latest Date	The date of the latest service call (in format: YYYY-MM- DD::hh-mm-ss-sss)
Latest User	The User ID of the user who issued the latest call

 (Optionally) Invoke the <u>reset</u> operation from the <u>PerformanceStatistics</u> Mbean to reset the statistics for the next collection period. Refer to the <u>Resetting Statistics</u> section for a discussion of this task.

This information can then be post processed in an appropriate analysis tool to determine appropriate actions.

Note: The statistics are active as long the Mbean is enabled, or the system is active. Shutting down the business application server with collection of the data may cause data loss for the statistics.

4.4.7 Service Lists

The JMX Performance Mbeans collect information about application services that have been executed during the collection period. This information can be obtained using the colledServices operation which returns a list of called services and their valid actions (summarized actions that have been called) in the format:

<servicename> [<valid action>]

Where,

Command Line Option	Description
<servicename></servicename>	Name of Service
<valid actions=""></valid>	List of valid actions recorded for the service. The table below lists the valid values.

Valid Action	Comment
ADD	Service is attempting to add a new instance of an object to the system. For example, adding a To Do record.
CHANGE	Service is attempting changes to an existing object in the system.
DEFAULT_ITEM	Service is resetting its values to defaults. For example, by pressing the <i>Clear</i> button on the product UI toolbar.
DELETE	Service is attempting to delete an existing object
EXECUTE_BO	Service is a business object
EXECUTE_BS	Service is a business service
EXECUTE_LIST	Service is a list-based service
EXECUTE_SEARCH	Service is a search
EXECUTE_SS	Service is a service script (including BPA scripts)
READ	Service is attempting to retrieve an object from the system
READ_SYSTEM	Service is a common Oracle Utilities Application Framework based service.
VALIDATE	Service is issuing a validation action

4.4.8 Resetting Statistics

The performance statistics collected represent values since the application was started or when it has been reset. Collection of statistics, without reset, can adversely influence the effectiveness of the statistics over time. It is therefore recommended to reset the statistics on a regular basis (after they are collected for example).

This can be achieved using the **reset** operation from the **PerformanceStatistics** Mbean to effectively zero or blank out the collection statistics.

For example, if the statistics are to be collected on an hourly basis, then the reset should occur after the data collection happens per hour.

Note: Any statistics collected during the actual reset operation will not be reflected in the statistics. This situation should have minimal impact on overall statistics.

4.5 Database Connection Monitoring

By default, your application uses a common database User ID for accessing the information from the connection pools used by the product (through the Universal Connection Pool (UCP)). While this sufficient for execution of the product, it can complicate monitoring individual connections and troubleshooting database issues with individual users or transactions.

It is now possible to show additional details that are inherited from the from the online and web services components. The following information is available from the connection and accessible from v\$session.

Parameter	Online	Web Service	Batch
CLIENT_IDENTIFIER	User ID	User ID	User ID

Parameter	Online	Web Service	Batch
MODULE	Service Name	Web Service Name	Batch Control
ACTION	Transaction Type	Transaction Type	Thread Number
CLIENT_INFO	Contents of Database Tag characteristic on User	"Web Service"	Threadpool Name

Note: Due to the length limitation on **CLIENT_IDENTIFIER** the value will be the authorization identifier and not the authentication identifier.

For example, the following database query will return the session ids and the users using then at any time:

SELECT sid, client identifier, module, client info, action FROM V\$SESSION;

The new information can be used to track sessions using the v\$session view, use more advanced features of the database and use other database options.

4.6 Probe Transaction

One of the monitoring facilities in your application is a probe transaction for the online component of the product. This is a set of JMX calls to the various components of the architecture to determine two sets of metrics:

- Availability of the component The availability will return a pass or fail on availability (including details is possible) of the component.
- Raw performance The raw transaction performance of the component from the call.

This represents the raw performance and should be used as a raw indication of performance at the network level.

The following components are tested using this capability:

Component	Test	Availability	Performance
Web Application Server	HTTP/HTTPS ping	RFC 2616 code	Time in ms
Business Application Server	Service Call	true or false	Time in ms
Database Server	SQL SELECT	True or SQL Error	Time in ms

The API is part of the **Business Application Server JMX Reference** facility.

Note: Customers using Application Management Pack for Oracle Utilities can use additional API's for performance and availability tracking.

5. Configuration

In this section you will find the necessary details (such as location, format, and usage) regarding the various configuration files that are implemented across the environment components.

5.1 Configuration Files

There are several configuration files that are implemented across the various components of the environment.

5.1.1 cistab - Global Configuration Files

The **cistob** file is a key configuration file for both the web application server and the database application server. It is built during the installation process and is used by Oracle Utilities Application Framework administration utilities to ensure that any output or log files generated by the product are stored in the correct location. It holds the mount points (for example, directories) used during the installation of the product to hold the product and its log files.

Location of cistab file:

/etc/cistab

A sample cistab file is outlined below:

DEV::/spl/DEV:/spl/sploutput/DEV::N

DEMO::/spl/DEMO:/spl/sploutput/DEMO::N

TEST::/spl/TEST:/spl/sploutput/TEST::N

TEST2::d:\spl\TEST2:e:\sploutput\TEST2::N

The format of the file is described below:

Position	Usage
1	Environment Name – specified at installation time. It is in UPPER case.
2	Reserved for future use.
3	Directory for the product software and configuration files (the SPLEBASE environment variable definition).
4	Directory for the product output files (the SPLOUTPUT environment variable definition).
5	Reserved for future use.
6	This flag may be used in custom start up scripts to indicate whether to start the environment at system boot time. Valid values are Y or N. This is the only setting that should be altered after installation.

Warning: Do not alter the **cistob** file unless instructed to do so by Oracle support personnel unless otherwise directed.

5.1.2 coherence-cache-config.xml - Oracle Coherence Configuration (BATCH)

The coherence-cache-config.xml configuration file is used by the CLUSTERED mode of execution to manage the Oracle Coherence based cache across the batch cluster. This file is generally not altered at the implementation level as it is preconfigured to execute the batch component of the ORMB application.

For details of the contents of this file refer to the *Oracle Coherence Integration Guide*.

5.1.3 e0Batch.properties - General Batch Properties

Note: This configuration file is generated and should not be altered unless instructed by Oracle Support.

This configuration file is used by the batch component to set the location of the installation and the location for any log files generated by the batch component.

This configuration file has two settings that are generated from the eOBatch.properties.template file located in templates directory:

Configuration Setting	Contents
standalone.dir	Location of batch installation
SPLOUTPUT	Location of output files

5.1.4 ejb-jar.xml - Enterprise Java Server Beans Configuration

The business application server and MDB functionalities use Enterprise Java Server beans to implement service calls. By default, the behavior of these components is defined and controlled with the ejb-jar.xml configuration file.

This configuration file is generated by the initialSetup using the templates/ejb- jar.xml.template file.

Note: This configuration file is typically NOT altered unless custom JMS or MDB resources are to be included in the servers within the application. Typically JMS resources are not included in the server Refer to the <u>Oracle WebLogic JMS Integration</u> (Document ID: 1308181.1) whitepaper for details of JMS or MDB advanced configuration.

5.1.5 ENVIRON.INI - Environment Configuration File

The <u>ENVIRON.INI</u> file is used by both the web application server and the business application server to define the environment and provide the basis for starting and stopping the environment. The file is created during the installation process and is used to generate other files. This file is maintained using the <u>configureEnv</u> utility provided in the installation. See <u>configureEnv – Set up Environment Settings</u>.

Warning! Do not alter the <u>ENVIRON.INI</u> manually. Always use <u>configureEnv</u> utility (see <u>configureEnv – Set up Environment Settings</u>) because additional configuration files depend on the settings in this file. If the configurations mismatch, improper operation of the product may occur.

Location of **ENVIRON.INI** file:

\$SPLEBASE/etc/ENVIRON.INI

The file contents are in text format and are of the form:

<parameter>=<value>

Where,

Command Line Option	Description
<pre><parameter></parameter></pre>	Name of configuration parameter
<value></value>	Value of the configuration parameter

For example:

. . .

appViewer=appViewer

DBCONNECTION=jdbc:oracle:thin:@myserver:1521:train

DBDRIVER=oracle.jdbc.driver.OracleDriver

DBNAME=TRAIN

. . .

The settings contained in the **ENVIRON.INI** file are outlined in **ENVIRON.INI**.

5.1.5.1 Extracting Information from ENVIRON.INI for Scripts

It is possible to write your own calls to the <u>ENVIRON.INI</u> using the same utilities used by your application to get values of configuration parameters for your own utilities. Do not hardcode values that can be obtained from <u>ENVIRON.INI</u>.

To obtain values of parameters use the command line:

perl \$SPLEBASE/bin/getconfvalue.plx -k <parameter>

Where,

Command Line Option	Description
<pre><parameter></parameter></pre>	Name of configuration parameter from <u>ENVIRON.INI</u> you desire to get the value of.

For example:

ENVIRON.INI content:

...

DBNAME=TRAIN

...

Example call:

\$ export DB='perl \$SPLEBASE/bin/getconfvalue.plx -k DBNAME'

\$ echo \$DB

TRAIN

Note: If the value is NOT set or the key is invalid the value of the call is null or blank.

5.1.6 hibernate.properties - Database Connectivity Settings

Opening a connection to a database is generally much less expensive than executing an SQL statement. A connection pool is used to minimize the number of connections opened between application and database. It serves as a librarian, checking out connections to application code as needed. Much like a library, your application code needs to be strict about returning connections to the pool when complete, for if it does not do so, your application will run out of available connections. Hence, the need for having a connection pooling mechanism such as Hibernate using Oracle <u>Universal Connection Pool</u> (UCP) connection pooling or JNDI based connection pooling.

The online and web service components of your application use JNDI based connection pools and the batch component uses UCP based connection pools.

Hibernate is a powerful Object Relational Mapping (ORM) technology that makes it easy to work with relational databases. Hibernate makes it seem as if the database contains plain Java objects, without having to worry about how to get them out of (or back into) database tables. Coupled with the UCP or JNDI connection pooler, it provides a comprehensive connectivity tool for the java to operate effectively against the database.

Oracle Utilities Application Framework applications use the Hibernate and either JNDI or UCP libraries to create a connection pool and connect the java objects to the database to store, update, delete and retrieve data. It is used for all the database access for online as well as batch.

Refer to http://www.hibernate.org for more information on the technology aspects of Hibernate and UCP.

Your application has a configuration file for the database connectivity and pooling called the hiter.properties configuration file. This file contains the configuration settings for the database connections and the connection pool to be used by any of the SQL statements accessing the database.

The configuration settings contained in the <u>hibernate.properties</u> file are summarized in the <u>hibernate.properties</u> section.

For a more indepth description of these parameters and others not included with the product, see http://www.hibernate.org.

5.1.7 log4j2.properties – Product Logging Configuration

Note: This log file should not be altered unless specified. The generated configuration file has all the recommended settings for all sites.

Oracle Revenue Management and Billing uses the log4j2 Java classes to centralize all log formats into a standard format. The details of the configuration settings and log4j2 itself are available at https://logging.apache.org/log4j/2.x/.

5.1.8 Server Jar File (ouaf_jar_versions.txt)

Points to Note:

This configuration file is used for internal purposes and should not be altered unless instructed to do so by Oracle Support.

Additional external jar files used for customizations do not need to be added to this file. This is used for base product verification only.

The java component of your application uses several industry standard jar files that are provided or used by the product. The **etc/ouaf_jar_versions.txt** lists the jar file that is used, and the required version used by the version of the product installed. This file is used at installation and runtime for integrity checks. If you wish to determine what version of an external jar is used, then refer to this information file.

5.1.9 spl.properties – Product Behaviour Settings

Oracle Utilities Application Framework web applications have settings outside of the JEE specification to control the internals of the product. This file exists as similar files exist for all modes of operation of the product (for example, Batch can be run outside the JEE web application server). Because of this a common configuration standard was adopted:

For a description of all settings in the <u>spl.properties</u> file refer to the <u>spl.properties</u> parameter descriptions.

5.1.10 submitbatch.properties - Submitter Configuration (BATCH)

Note: This is the default configuration file. Refer to the <u>Configuring Batch Using Bedit</u> section for a discussion of the role of this configuration and its variations

Each background process requires a configuration file to control its behavior. There are two levels of files that control the individual batch job executions:

- <u>submitbatch.properties</u> This file sets the global settings for all batch jobs that are submitted. This file is in **\$SPLEBASE**/splapp/standalone/config directory.
- <batchcode>.properties This file is the same format as submitbatch.properties but contains any job specific settings and/or overrides to settings in the submitbatch.properties.

Note: Any command line options can override settings in any configuration file.

This file is generated using the bedit facility. See Configuring Batch Using Bedit.

5.1.11 tangosol-coherence-override.xml - Coherence Overrides (BATCH)

The tangosol-coherence-override.xml configuration file is used by the **CLUSTERED** mode of execution to override the settings for the Oracle Coherence based cache across the batch cluster. This file is generally not altered at the implementation level as it is preconfigured to execute the batch component of the ORMB application.

This file is generated using the bedit utility. See Configuring Batch Using Bedit.

For details of the contents of this file refer to the *Oracle Coherence Integration Guide*.

5.1.12 threadpoolworker.properties - Threadpool Configuration (BATCH)

Note: This is the default configuration file. Refer to the <u>Configuring Batch Using Bedit</u> section for a discussion of the role of this configuration and its variations

Each threadpoolworker requires a configuration file to control its behavior. This file is generated using the <u>bedit</u> facility for each type of threadpoolworker. See <u>Configuring Batch Using Bedit</u>.

Note: Any command line options on **threadpoolworker.sh** utility can override settings in any configuration file. See <u>threadpoolworker.sh</u> - <u>Manage Threadpools</u> for details.

This file is generated using the <u>bedit</u> facility. See <u>Configuring Batch Using Bedit</u> for details.

5.1.13 web.xml – JEE Deployment Descriptor

Note: For inbound web services, a resource version of this file is generated.

The web deployment descriptor editor lets you specify deployment information for modules created in the web development environment.

The information appears in the <u>web.xml</u> file. The <u>web.xml</u> file for a web project provides information necessary for deploying a web application module. It is used in building a WAR/EAR file from a project.

The web application is controlled by a configuration file that holds behavioral information for the applications. Refer to http://jcp.org/en/jsr/detail?id=109 for more details of the format.

For example:

```
<env-entry-value>false</env-entry-value>
  <env-entry-type>java.lang.Boolean</env-entry-type>
</env-entry>
<env-entry>
  <description>Preload ALL Pages</description>
  <env-entry-name>preloadAllPages</env-entry-name>
  <env-entry-value>false</env-entry-value>
  <env-entry-type>java.lang.Boolean</env-entry-type>
</env-entry>
  <description>Disable preloading of Pages</description>
  <env-entry-name>disablePreload</env-entry-name>
  <env-entry-value>false</env-entry-value>
  <env-entry-value>false</env-entry-value>
  <env-entry-type>java.lang.Boolean</env-entry-type>
</env-entry>
```

For application specific entries, refer to the web.xml section.

Note: It is highly recommended that you do not change this configuration file by extracting the configuration file from the WAR/EAR file using Java utilities, making the change manually and rebuilding the WAR/EAR file. Use <u>initialSetup — Maintain Configuration Settings</u> to build the WAR/EAR file as documented in the Web Application Server Configuration Process.

5.1.14 weblogic.xml – Oracle WebLogic Extensions

Note: For inbound web services, a resource version of this file is generated.

For backward compatibility with Oracle WebLogic environments, an additional Oracle WebLogic configuration file weblogic.xml is generated and used to influence the Oracle WebLogic Server to exhibit additional behavior.

Parameter	Context	Source
context-root	The context-root element defines the context root of this stand-alone web application. If the web application is part of an EAR, not standalone, specify the context root in the EAR's web.xml file. A context-root setting in web.xml takes precedence over context-root setting in weblogic.xml.	Defaults from template
java-charset- name	Specifies the Java character set to use.	Defaults from template (UTF-8)

Parameter	Context	Source
page-check- seconds	Determines the interval at which a server checks to see if JSP files in a web application have changed and need recompiling. Used for development.	Derived from WEB_WLPAGECHECKSECO NDS parameter from ENVIRON.INI
prefer-web-inf- classes	Loading of web classes from the WEB-INF are loaded in preference to system or Oracle WebLogic classes. Defaulted to false.	Defaults from template
resource-path	A path which, if included in the URL of a request, signals Oracle WebLogic Server to use the Java character set specified by javacharset-name.	Defaults from template
servlet-reload- check-secs	Defines whether an Oracle WebLogic Server will check to see if a servlet has been modified, and if it has been modified, reloads it. The -1 value tells the server never to check the servlets, 0 tells the server to always check the servlets, and the default is to check each 1 second. A value specified in the console will always	
	take precedence over a manually specified value.	
url-rewriting- enabled	Provides methods for configuring a JEE web application that is deployed on an Oracle WebLogic Server instance. Oracle WebLogic Server instantiates this interface only when you deploy a web application. This interface can configure web applications that are deployed as a WAR file or an exploded directory.	Defaults from template (false)

Note: This configuration file is not usually altered by an implementation as it applies to development (SDK) platforms only. It is documented for completeness here.

Example:

5.1.15 weblogic-ejb-jar.xml – WebLogic Extensions for Enterprise Java Server Beans

Oracle WebLogic Server-specific EJB deployment descriptor that contains elements related to Oracle WebLogic Server features such as clustering, caching, and transactions. This file is required if your beans take advantage of Oracle WebLogic Server-specific features.

This file is coupled with the <u>ejb-jar.xml</u> configuration file using the standard <u>weblogic-ejb-jar.xml</u> schema. This configuration file is generated by the <u>initialSetup – Maintain Configuration Settings</u> using the <u>templates/weblogic-ejb-jar.xml.template</u> file.

Note: This configuration file is typically NOT altered unless custom JMS or MDB resources are to be included in the servers within the application. Typically JMS resources are not included in the server Refer to the <u>Oracle WebLogic JMS Integration</u> (Document ID: 1308181.1) reference paper for details of JMS or MDB advanced configuration.

5.1.16 webservices.xml.resource - Web Services Configuration

Note: This file is automatically generated and should not be altered manually unless instructed by Oracle Support.

When using inbound web services, a web services deployment descriptor, <u>webservices.xml</u>, must be generated to inform the JEE web application server of the web services.

This file is automatically generated from the template file webservices.xml.resource.iws.template located in the templates directory.

5.2 Web Browser Configuration

Oracle Utilities Application Framework applications are browser-based (browsers, versions and platforms are documented in the *Oracle Revenue Management and Billing Installation Guide* for your platform. Additionally, the following settings are applicable to the browser:

 Mozilla Firefox/Google Chrome/Microsoft Edge - Use the default settings with the browser for the browser.

Note: Clearing the cache upon exit will clear the cached screens of the product as well.

• The product requires support for the HTTP 1.1 protocol to support compression and client cache management.




Figure 16: HTTP 1.1 Settings

Note: If a network proxy is used then "Use HTTP 1.1 through proxy connections" may need to be selected as well.

The product uses Java scripting for user interactivity. Therefore, the **Allow sites to run Javascript** option (Google Chrome/Microsoft Edge) in Content Settings and **javascript.enabled** (Mozilla Firefox) in about:config must be set to **true**.

Note: By default, Mozilla Firefox, Microsoft Edge, and Google Chrome enable Javascript automatically.




Figure 17: Javascript Settings

The product uses pop-up windows for searches; therefore, pop-up blockers should be configured
to allow pop-ups from the product web application server hosts. Add the Application URL by
adding an exception using the relevant function in the browser.

Note: Some browsers allow users to add an exception at runtime. Refer to the browser documentation for more information.

Set your browser cache size to a reasonable size to hold the cached pages as needed.

5.3 Web Application Server Configuration

5.3.1 Web Application Server Concepts

Each web application server has several levels, and each uses different terminology. The following terminology will be used:

- The software exists on a physical machine.
- An installation of the Web Application Software is called an instance. Typically, one instance of the software exists on a machine, but you can have more than one installed.
- Within an instance you can define a server. This is also called a Java container which will house one or more applications. You will have at least one server per environment. A server uses one Java Virtual Machine (JVM).
- Within a server is the application. It can be a single application or multiples depending on the web application server supported.

The web application server you use may have different terminology for these same concepts. For the remainder of this section, we will use the above terminology.

5.3.2 Web Applications

Your application is deployed as a set of web applications within the web applications server:

• **root** - This is the product itself is installed.

Note: Appviewer has been deprecated and javadocs are deployed as a distinct war file in the splweb.ear.

• **Webservices** - This is the web services component.

Note: XAI supported in earlier versions of the product has been replaced by inbound web services. Customers using XAI should migrate to inbound web services. For a discussion of this process refer to <u>Migrating from XAI to IWS</u> (Document ID: 1644914.1) available from <u>My Oracle Support</u>.

- appViewer An Application Viewer that contains a data dictionary and source viewer.
- help Online Help.

5.3.3 Web Application Server Configuration Files

Within each JEE Web Application, the JEE web application server has its own configuration files. These files are typically embedded within the WAR/EAR files deployed with the product following the JEE specification. In terms of configuration, the product structure within the WAR/EAR file looks like the following:




Figure 18: Configuration File Hierarchy

Configuration File	Contents
hibernate.properties - Database Connectivity Settings	Database connectivity
log4j2.properties – Product Logging Configuration	Logging configuration
spl.properties - Product Behaviour Settings	Behavior configuration
web.xml - JEE Deployment Descriptor	Deployment Descriptor
weblogic.xml – Oracle WebLogic Extensions	WebLogic extensions

5.3.4 Web Application Server Configuration Process

To configure the web application server during the installation process and post-installation then the following process should be used:




Figure 19: Web Application Server Configuration Process

The <u>configureEnv – Set up Environment Settings</u> utility is used during installation time and can be used post implementation to set parameters in the <u>ENVIRON.INI</u>. If any parameters are derived or set from the <u>ENVIRON.INI</u> (see the Source column in the relevant section) then the <u>configureEnv – Set up Environment Settings</u> utility should be used to maintain them.

Note: The <u>configureEnv – Set up Environment Settings</u> utility should be used to make any changes to the <u>ENVIRON.INI</u>. Manual changes to this configuration file are not recommended.

- After the <u>ENVIRON.INI</u> has been set or altered, the settings must be reflected in the relevant configuration files used by the web application server by running the <u>initialSetup – Maintain</u> <u>Configuration Settings</u> utility:
 - o web.xml JEE Deployment Descriptor
 - o <u>log4j2.properties Product Logging Configuration</u>
 - o spl.properties Product Behaviour Settings
 - o weblogic.xml Oracle WebLogic Extensions
- The utility uses the templates from the templates directory to create substituted copies of these
 files in a standard location. The table below lists the configuration file, the templates used from
 the templates directory and the final configuration built during the initial configuration process:

Configuration File	Destination
Online Application (root)	
web.xml - JEE Deployment Descriptor	\$SPLEBASE/etc/conf/WEB-INF
Template:	
web.xml.template	
spl.properties - Product Behaviour Settings	\$SPLEBASE/etc/conf/root/WEB-INF/classes

Configuration File	Destination
Template:	Destination
spl.properties.template	
log4j2.properties – Product Logging	\$SPLEBASE/etc/conf/root/WEB-INF/classes
Configuration	
Template:	
log4j2.properties.template	
weblogic.xml – Oracle WebLogic Extensions	\$SPLEBASE/etc/conf/root/WEB-INF
Template:	
weblogic.xml.template	
REST Server	
web.xml - JEE Deployment Descriptor	\$SPLEBASE/etc/conf/WEB-INF
Template:	
web.xml.rest.template	
spl.properties - Product Behaviour Settings	\$SPLEBASE/etc/conf/rest/WEB-INF/classes
Template:	
spl.properties.rest.template	
log4j2.properties – Product Logging	\$SPLEBASE/etc/conf/rest/WEB-INF/classes
Configuration	
<pre>Template: log4j2.properties.rest.template</pre>	
	ACDI EDACE / / / //ATED INTE
<pre>weblogic.xml - Oracle WebLogic Extensions Template:</pre>	\$\$PLEBASE/etc/conf/rest/WEB-INF
weblogic.xml.rest.template	
Application Viewer (appViewer)	
web.xml - JEE Deployment Descriptor	¢CDI ERACE/ota/conf/IA/ER INIE
Template:	\$SPLEBASE/etc/conf/WEB-INF
web.xml.appViewer.template	
weblogic.xml – Oracle WebLogic Extensions	\$SPLEBASE/etc/conf/appViewer/WEB-INF
Template:	got bibliobjete, collijapp viewelj vvib iivi
weblogic.xml.appViewer.template	
Help Application (help)	
spl.properties - Product Behaviour Settings	\$SPLEBASE/etc/conf/ohelp
Template:	got 222102/etc/colli, olicip
spl.properties.ohelp.template	
	ı

• At this point you may perform manual changes to the above files to parameters not implemented in the ENVIRON.INI.

Note: Any manual changes are overwritten after running the <u>initialSetup</u> utility unless the change is reflected in the appropriate template (see <u>initialSetup – Maintain Configuration Settings</u> and <u>Implementing Custom Templates</u> for more information). Backups should be made of any changes and then manually reapplied to reinstate all manual changes.

- To reflect configuration changes into the web applications, the <u>initialSetup</u> utility with the <u>-w</u> option must be executed (see <u>initialSetup Maintain Configuration Settings</u>). This will build the necessary WAR/EAR files to be deployed into Oracle WebLogic. This step is optional if configuration overrides are in use.
- Depending on the architecture, the <u>initialSetup</u> will generate one or more EAR files. Refer to the <u>Business Application Server Configuration</u> for a description of the EAR files.
- At this point the product web applications are ready for deployment into the JEE web application server.

5.3.5 Quick Reference Guide for Web Application Server Configuration

To make configuration changes to the web application server component of Oracle Revenue Management and Billing, use the following Quick Reference Guide to identify which process are to be used:

- If the change is to any setting contained in the ENVIRON.INI for the web application server then you must run the following utilities in the order indicated:
 - 1. Execute the <u>configureEnv</u> utility to reflect the parameter change in the <u>ENVIRON.INI</u>. See the <u>configureEnv</u> <u>Set up Environment Settings</u> for details.
 - 2. Execute the <u>initialSetup</u> utility (with the –t option) to rebuild the configuration files using the <u>ENVIRON.INI</u> and provided template files. This will reset the configuration to the contents of the base template files or custom template (if used). See <u>initialSetup</u> <u>Maintain Configuration Settings</u> for details.
 - 3. Any configuration changes that are overridden by templates (base or custom) must be manually reapplied (if necessary).
 - 4. Execute the <u>initialSetup</u> utility (with the **-w** option) to implement the configuration files in the product web application server files. This step is not necessary of you are using configuration overrides. See <u>initialSetup</u> <u>Maintain Configuration Settings</u> for details.
- If the change is to any setting not contained in the ENVIRON.INI for the web application server but is in the configuration files for the web application server, then you must run the following utilities in the order indicated:
 - 1. Make any manual changes to the relevant configuration files.
 - 2. Execute the <u>initialSetup</u> (with the **-w** option) utility to implement the configuration files in the product web application server files. This step is not necessary of you are using configuration overrides. See <u>initialSetup</u> <u>Maintain Configuration Settings</u> for details.
- If native installation is used, it is recommended to redeploy or update the generated EAR files from the relevant command or console.

5.3.6 User Interface Backward Compatibility Settings

The following settings are used for backward compatibility of the User interface for customers upgrading in the <u>spl.properties</u> file from an Oracle Utilities Application Framework V2.1 based product (values of true emulate V2.1 user interface behavior for UI Maps):

- <u>spl.runtime.compatibility.uiMapDisableInputValue Map Defaults</u> By default, if the XML schema has an input value with a default, then setting this value to false will cause the product to set this value to blank and ignore the default value for add mode in all UI Maps. Setting of this value to true will cause the default to be displayed in the input field for add mode in all UI Maps. The default value for this parameter is false.
- spl.runtime.compatibility.uiMapDropdownSelectFirstValue Drop-down Defaults By default, dropdown widgets on UI Maps are defaulted to no value to force the user to select a value. By setting this parameter to true, forces all drop-downs on all UI Maps to automatically default to the first value in the drop-down list. By setting this value to false, the default, the UI Maps will have blank values as the default value for the drop-downs.
- spl.runtime.compatibility.uiMapDisableTitle Screen Title Defaults By default UI Maps contain a
 rendered title section. By setting this parameter to true, the title sections for all UI Maps are not
 automatically rendered. By setting this parameter to false, the default, title sections are rendered
 automatically for all UI Maps.
- spl.runtime.compatibility.uiMapDisableGenerateUniqueHtmlIDs Map Ids By default screen
 elements have unique ids for reference, including individual records in lists or queries. By setting
 this value to false, the default, the framework will generate unique ids for ADA compliance. If
 customizations from past releases have issues with these unique IDs, then setting the value to true
 will revert to behavior available in past releases of Oracle Utilities Application Framework
 applications.

Note: It is recommended to leave the default value, false, for these parameters unless otherwise required or instructed by Oracle Support.

5.3.7 Web Application Server Deployment Process

After the configuration of the Web Application is complete (as outlined in <u>Web Application Server Configuration Process</u>) the final step to implement the product technically is to deploy the product within the JEE web application server.

There are three methods of deploying the product within the JEE web application server:

 Use the deployment utilities provided on the console of the JEE web application server. The WAR/EAR files that are available under \$SPLEBASE/splapp/applications can be manually deployed using the console. Refer to the Oracle Revenue Management and Billing Installation Guide for specific platform instructions and the administration guide for the JEE web application server.

Note: This is the only method that can be used if virtual web application servers are used with the product.

- Use the deployment utilities provided on the command line of the JEE web application server. The WAR/EAR files that are available under \$SPLEBASE/splapp/applications can be manually deployed using the command line utilities supplied with Oracle WebLogic. Refer to the Oracle Revenue Management and Billing Installation Guide for specific platform instructions and the Oracle WebLogic Administration Guide.
- 3. Several specific utilities from Oracle WebLogic are provided with the product to deploy the web application to the JEE web application server. These call the same utilities provided in Option 2 but are provided with the product.

Note: This section will outline only option 3.

Several utilities are provided with Oracle WebLogic to deploy the ORMB application to the domain. These utilities are summarized below:




Figure 20: Web Application Server Deployment Process

Use the Oracle WebLogic console, Fusion Middleware Control or WLST to deploy/redeploy the EAR files. The Web Application should be available from the web application server.

5.4 Business Application Server Configuration

It is possible for the business application server's logic to be separated from the web application server component. Essentially, your application has been split into two distinct EAR files:

- **SPLWeb.ear** (<u>SPLWEBAPP Name of Web Application Server Application</u>) This contains the web application server component for the product.
- **SPLService.ear** (<u>SPLSERVICEAPP Name of Business Application Server Application</u>) This contains the business application server component for the product. There are two modes of installation:




Figure 21: Installation Modes

Local Installation (also applicable to expanded installations for Development environments) - The
web application server and business application are on the same instance of the JEE web
application server. This is the default behavior of the product for backward compatibility. If this is
the mode installed then for configuration the process is a combination of the <u>Web Application</u>
<u>Server Configuration</u> and <u>Business Application Server Configuration</u> and deployment process.

Note: Local installations are recommended for all environments.

- Decoupled Installation The business application server is on a separate instance of the JEE web application server. This may be the same machine or different machines. In this case the <u>Web Application Server Configuration</u> and <u>Business Application Server Configuration</u> are managed and configured separately. To perform a decoupled installation the following must be performed:
 - 1. The product is installed on the machines housing the <u>Web Application Server Configuration</u> and <u>Business Application Server Configuration</u>.
 - 2. A set of servers within one or more instances of the JEE web application server must be created to house the <u>Web Application Server Configuration</u> and the <u>Business Application Server Configuration</u> separately. This can be on the same machine or across machines.
 - 3. The web and business application servers are configured as outlined in <u>Web Application</u> <u>Server Configuration</u> and <u>Business Application Server Configuration</u>.
 - 4. The WAR/EAR files generated are deployed separately with the SPLWeb.ear (or set by SPLWEBAPP Name of Web Application Server Application) EAR file deployed to the web application server as outlined in Web Application Server Deployment Process and SPLService.ear EAR file (or set by SPLSERVICEAPP Name of Business Application Server Application) deployed to the Business Application Server Configuration as outlined in Business Application Server Deployment Process.

Note: For customers using Oracle ExaLogic, Oracle highly recommend that local installations be used for performance reasons.

5.4.1 Business Application Server Concepts

As previously mentioned, the business application server component can be deployed within a separate instance of the JEE web application server software. This effectively allows the business application server to be on separate hardware for architectures where this is a requirement. Typically, this separation is implemented for a number of reasons:

- The site has an architectural principle for separating the web and the business application servers.
- The site prefers to optimize the individual servers for the individual tiers rather than having to compromise when two or more tiers are on the same platform.

The business application server was designed to fit within the same concepts as the web application server. The main differences are:

- Enterprise Java Beans (stateless) are used in the business application server instead of the Java Server Pages, which are used in the web application server. The name of the EJB is splservicebean where <version> is the version of the product, for exampe: 2.0.0).
- Database connectivity is configured in the business application server.

The rest of this section will outline the differences specifically for the business application server.

5.4.2 Business Application Server Configuration Files

Each JEE web application within the JEE web application server has its own configuration files. These files are typically embedded within the WAR/EAR files deployed with the product following the JEE specification (refer the discussion of allowing the externalization of configuration settings for alternative methods). In terms of configuration, your application's structure within the WAR/EAR file is as follows:

Configuration File	Contents
ejb-jar.xml - Enterprise Java Server Beans Configuration	Enterprise Service Bean configuration
<u>hibernate.properties - Database Connectivity</u> <u>Settings</u>	Database connectivity
log4j2.properties – Product Logging Configuration	Logging configuration
spl.properties - Product Behaviour Settings	Behavior configuration
web.xml - JEE Deployment Descriptor	Deployment Descriptor
weblogic.xml – Oracle WebLogic Extensions	Oracle WebLogic extensions
weblogic-ejb-jar.xml – WebLogic Extensions for Enterprise Java Server Beans	Oracle WebLogic extensions for Enterprise Service Bean configuration

5.4.3 Business Application Server Configuration Process

To configure the business application server during the installation process and post-installation then the following process should be used:




Figure 22: Business Application Server Configuration Process

The <u>configureEnv – Set up Environment Settings</u> utility is used during installation time and can be used post implementation to set parameters in the <u>ENVIRON.INI</u>. If any parameters are derived or set from the <u>ENVIRON.INI</u> (see the Source column in the relevant section) then the <u>configureEnv</u> utility should be used to maintain them.

Note: The <u>ENVIRON.INI</u> utility should be used to make ANY changes to the <u>ENVIRON.INI</u>. Manual changes to this configuration file are not recommended.

- After the <u>ENVIRON.INI</u> has been set or altered, the settings must be reflected in the relevant configuration files used by the business application server by running the <u>initialSetup</u> (see <u>initialSetup – Maintain Configuration Settings</u>):
 - log4j2.properties
 - spl.properties
 - o <u>hibernate.properties</u>
 - o web.xml
 - o weblogic.xml
 - o <u>ejb-jar.xml</u>
 - o weblogic-ejb-jar.xml

The utility uses the templates from the templates directory to create substituted copies of these files in a standard location:

Configuration File	Destination
Service Bean	
<pre>web.xml - JEE Deployment Descriptor Template: web.xml.template</pre>	\$SPLEBASE/etc/conf/WEB-INF
<pre>spl.properties - Product Behaviour Settings Template: spl.properties.service.templat e</pre>	\$SPLEBASE/etc/conf/service \$SPLEBASE/splapp/businessapp/properties
<pre>log4j2.properties - Product Logging Configuration Template: log4j2.properties.service.temp late</pre>	\$SPLEBASE/etc/conf/service \$SPLEBASE/splapp/businessapp/properties
hibernate.properties - Database Connectivity Settings Template: hibernate.properties.web.templ ate	\$SPLEBASE/etc/conf/service
<pre>ejb-jar.xml - Enterprise Java Server Beans Configuration Template: ejb-jar.xml.template</pre>	\$SPLEBASE/splapp/businessapp/config/META-INF
<pre>weblogic-ejb-jar.xml - Weblogic Extensions for Enterprise Java Server Beans Template: weblogic-ejb-jar.xml.template</pre>	\$SPLEBASE/splapp/businessapp/config/META-INF

The locations of the configuration files can be summarized in the following figure:




Figure 23: Business Application Server Configuration Files

 At this point you may perform manual changes to the above files to parameters not implemented in the ENVIRON.INI.

Note: Any manual changes are overwritten after running the <u>initialSetup</u> utility unless the change is reflected in the appropriate template (see <u>initialSetup – Maintain Configuration Settings</u> and <u>Implementing Custom Templates</u> for more information). Backups should be made of any changes and then manually reapplied to reinstate all manual changes.

• To reflect configuration changes into the product Business EJB Applications the initialSetup utility, with the –w option, must be executed (see initialSetup — Maintain Configuration Settings). This will build the necessary <a href="spl-servicebean-<version">spl-servicebean-<version,jar (where version is the version of the product used) and the SPLService.ear EAR file (or name set by SPLSERVICEAPP-Name of Business Application Server Application) to be deployed into the Oracle WebLogic Domain. This step is optional if configuration overrides are in use (refer the discussion of allowing the externalization of configuration settings for alternative methods).

Depending on the architecture used, the <u>initialSetup</u> will generate one or more EAR files. At this point the product business applications are ready for deployment into the Oracle Weblogic Domain.

5.4.4 Quick Reference Guide for Business Application Server Configuration

To make configuration changes to the business application server component of the ORMB application, use the following Quick Reference Guide to identify which process should be used:

- If the change is to any setting contained in the <u>ENVIRON.INI</u> for the business application server, then you must run the following utilities in the order indicated:
 - 1. Execute the <u>configureEnv Set up Environment Settings</u> utility to reflect the parameter change in the <u>ENVIRON.INI</u>.
 - 2. Execute the <u>initialSetup</u> utility (using the –t option) to rebuild the configuration files using the <u>ENVIRON.INI</u> and provided template files. This will reset the configuration to the contents of the base template files or custom template (if used). See <u>initialSetup</u> <u>Maintain Configuration Settings</u> for details.
 - 3. Any configuration changes that are overridden by templates (base or custom) must be manually reapplied (if necessary).
 - 4. Execute the <u>initialSetup</u> utility (with the –w option) to implement the configuration files in the product business application files. This step is not necessary of you are using configuration overrides.
- If the change is to any setting not contained in the <u>ENVIRON.INI</u> for the business application server but is in the configuration files for the business application server, then you must run the following utilities in the order indicated:
 - 1. Make any manual changes to the relevant configuration files.
 - Execute the <u>initialSetup</u>, with the -w option, utility to implement the configuration files in the Oracle Revenue Management and Billing business application server files. This step is not necessary of you are using <u>configuration overrides</u>.

5.4.5 Business Application Server Deployment Process

After the configuration of the business application server is complete (as outlined in business application server Configuration Process), the final step to implement your application is to deploy the product within the JEE web application server.

There are three methods of deploying the product within the JEE web application server:

- Use the deployment utilities provided on the console of the JEE web application server. The WAR/EAR files that are available under \$SPLEBASE/splapp/applications can be manually deployed using the console. Refer to the Oracle Revenue Management and Billing Installation Guide for specific platform instructions and to the Administration Guide for the JEE web application server.
- Use the deployment utilities provided on the command line of the JEE web application server. The
 WAR/EAR files that are available under \$SPLEBASE/splapp/applications can be manually
 deployed using the JEE web application server vendor supplied deployment command line
 utilities. Refer to the Oracle Revenue Management and Billing Installation Guide for specific
 platform instructions and the administration guide for the JEE web application server.
- Several specific utilities for JEE web application are provided with the product to deploy the EJB
 application to the JEE web application server. These call the same utilities provided in the previous
 option but are provided with the product.

This section will outline the latter option.

Several specific utilities from Oracle WebLogic are provided with the product to deploy the Web Application to the domain. These utilities are outlined below:




Figure 24: Business Application Server Deployment Process

Use the Oracle WebLogic console, Fusion Middleware Control or WLST to deploy/redeploy the EAR files.

5.5 Inbound Web Services Configuration

Oracle Utilities Application Framework applications support the ability to implement product web services within the JEE web application server instead of being accessible from the XML Application Integration (XAI) servlet. This has several advantages:

- Inbound web services can utilize the clustering and high availability features of the JEE web application server directly.
- Individual inbound web services can be monitored from the JEE web application server directly. If
 Oracle Enterprise Manager is used, performance and diagnostic metrics on individual inbound
 web services can be collected and analyzed for service level tracking and general monitoring.
- Individual inbound web services can be secured using the WS-Policy support available in the JEE web application server directly. Customer using Oracle WebLogic Server can also utilize the inbuilt Oracle Web Services Manager within Oracle WebLogic to add access rules to individual web services.

Note: It is required to use inbound web services instead of XML Application Integration as the XAI Servlet has been deprecated.

5.5.1 Enabling Inbound Web Services

By default, for backward compatibility, the inbound web services feature is disabled. To use the feature, it must be enabled and a few features enabled to use the deployment facilities provided by this capability. All these steps must be executed by the relevant administrator user as indicated in the individual steps.

Note: These steps, unless otherwise indicated, are performed once per environment.

5.5.1.1 Enable Inbound Web Services Feature

Note: Customers using the application's native installation should ensure that the <u>WEB_WLS_SVRNAME</u> is set to the name of the server or cluster used for the environment.

The first step is to enable the feature in the environment configuration file (ENVIRON.INI - Environment Configuration File) to use additional facilities:

- Using the product administrator user on the machines where the product is installed, execute the configureEnv.sh —a command after executing the splenviron.sh —e <environmentname> where <environmentname> is the name of the installation environment to enable the feature upon. See configureEnv Set up Environment Settings and splenviron Set Environment Variables for details.
- Change the option Enable Web Services Functionality on option 50 to true. Save the change using the "P" option.
- Execute the <u>initialSetup.sh</u> command to apply the changes to the infrastructure and generate the
 necessary build files for inbound web services. See <u>initialSetup Maintain Configuration Settings</u>
 for details.

5.5.1.2 Set Credentials for Inbound Web Services

Note: Failure to perform this task may cause the deployment of inbound web services to fail.

To deploy the inbound web services seamlessly it is necessary to create an administration credential file so that the build and deployment utilities and online deployment facility for developers can access the domain.

To create this credential file the following commands must be executed:

- Using the product administrator user on the machines where the product is installed, execute the splenviron.sh utility —e <environmentname> where <environmentname> is the name of the installation environment to enable the feature upon. See splenviron Set Environment Variables for details.
- Execute the following command:

\$JAVA_HOME/bin/java -classpath \$WL_HOME/server/lib/weblogic.jar weblogic.Admin -username <username>-password <password> STOREUSERCONFIG -userconfigfile \$SPLEBASE/etc/.wlsuserconfig -userkeyfile \$SPLEBASE/etc/.wlsuserkey

Where <username> is an Administration password for the domain and <password> is the password for that user. For example, these values can correspond to WEB_WLSYSUSER and WEB_WLSYSPASS (in plain text).

Note: If the password for this user is changed at any time, this step must be repeated for the facility to continue to operate.

5.5.1.3 Enable USER_LOCK Facility

To prevent multiple parallel deployments, the **USER_LOCK** feature of the database must be enabled on the product user. The following commands must be executed:

- Log into the database using SQL Developer or SQL Plus the SYS or SYSTEM user.
- Execute the following command:

@?/rdms/admin/userlock.sql

Note: ? corresponds to ORACLE_HOME.

• Grant access to the product user using the following command:

grant execute on USER_LOCK to <user>;

where <user> is the DBUSER and BATCH_DBUSER from the ENVIRON.INI. See DBUSER - Online Database User and BATCH_DBUSER - Batch User for details.

Note: BATCH DBUSER is used for command line deployment.

5.5.2 Inbound Web Services Configuration Files

The location of the inbound web service is as follows:




Figure 25: Inbound Web Services Configuration

The following configuration files apply to the inbound web service:

Configuration File	Contents
<u>hibernate.properties – Database Connectivity</u> <u>Settings</u>	Database connectivity for inbound web services
log4j2.properties – Product Logging Configuration	Logging configuration
spl.properties – Product Behavior Settings	Inbound web service specific configurations
weblogic.xml – Oracle WebLogic Extensions	WebLogic extensions
weblogic-ejb-jar.xml - Weblogic Extensions for Enterprise Java Server Beans	WebLogic extensions for inbound web services
weblogic-webservices-policy.xml – Web Services Configuration	Authentication policies applicable for IWS

5.5.3 Inbound Web Services Concepts

The inbound web services deploys a web archive (WebServices.ear or name set by <u>IWSWAR - Name of Inbound Web Services WAR</u>) containing the components of the inbound web services using the following structures:




Figure 26: Inbound Web Services Structures

Structure	Contents
config	Inbound Web Services Configuration
gen	Location of files generated by iwsdeploy – Inbound Web Services Deployment
lib	Java Libraries
resources	Inbound Web Services Configuration, custom policy, XSL, and XSD files
policies	Configuration files defining security policies for inbound web services

The inbound web services was designed to fit within the same concepts as the web application server/business application Services. The main differences are:

 The Webservices.ear file (or name set by <u>IWSWAR - Name of Inbound Web Services WAR</u>) is located in the <u>\$SPLEBASE/splapp/iws/gen</u> directory and is deployed automatically using <u>iwsdeploy.sh</u> or the online deployment facility.

Note: Customers using native installation can optionally manually deploy the war file, if desired.

Database connectivity is configured in the inbound web services and included in the build file.

5.5.4 Inbound Web Services Configuration Process

Note:

This section only covers the configuration and deployment of the physical web service resources. It does not cover the definition of inbound web services within the application. Refer to the <u>Migrating XAI to IWS</u> (Document Id: 1644914.1) available from My Oracle Support for more details on Inbound Web Services.

For this feature to operate, at least one inbound web service should be defined for the build process to execute. If no inbound web services are defined prior to the deployment, then the build process will fail.

To configure the inbound web services during the installation process and post-installation then the following process should be used:




Figure 27: Inbound Web Services Configuration Process

 The <u>configureEnv</u> utility is used during installation time and can be used post implementation to set parameters in the <u>ENVIRON.INI</u>. If any parameters are derived or set from the <u>ENVIRON.INI</u> (see the "Source" column in the relevant section) then the <u>configureEnv</u> utility should be used to maintain them, See <u>configureEnv</u> – <u>Set up Environment Settings</u> for details.

Note: The <u>configureEnv</u> utility should be used to make ANY changes to the <u>ENVIRON.INI</u>. Manual changes to this configuration file are not recommended.

 After the <u>ENVIRON.INI</u> has been set or altered, the settings must be reflected in the relevant configuration files used by the inbound web services by running the <u>initialSetup.sh</u> -t: See <u>initialSetup</u> – <u>Maintain Configuration Settings</u> for details. • The utility uses the templates from the **templates** directory to create substituted copies of these files in a standard location:

Configuration File	Destination
Inbound Web Services	
spl.properties – Product Behavior Settings	Database connectivity for inbound web services
<u>Template</u> :	
spl.properties.iws.template	
log4j2.properties - Product Logging Configuration	Logging Configuration
Template:	
log4j2.properties.iws.template	
<u>hibernate.properties</u> – <u>Database</u>	Inbound web service specific configurations
Connectivity Settings	
Template:	
hibernate.properties.iws.template	
web.xml – JEE Deployment Descriptor	WebLogic extensions
<u>Template</u> :	
web.xml.resource.iws.template	
webservices.xml.resource – Web Services	WebLogic extensions for inbound web services
Configuration	
<u>Template</u> :	
webservices.xml.resource.iws.temp	
late	
weblogic.xml – Oracle WebLogic Extensions	Authentication policies applicable for IWS
<u>Template</u> :	
weblogic.xml.iws.template	

 At this point you may perform manual changes to the above files to parameters not implemented in the <u>ENVIRON.INI</u>.

Note: Any manual changes are overwritten after running the <u>initialSetup</u> utility unless the change is reflected in the appropriate template (see <u>initialSetup - Maintain Configuration Settings</u> and <u>Implementing Custom Templates</u> for more information). Backups should be made of any changes and then manually reapplied to reinstate all manual changes.

To reflect configuration changes into the product the <u>iwsdeploy</u> utility, must be executed (see <u>iwsdeploy</u> – <u>Inbound Web Services Deployment</u>). This will build the necessary <u>Webservices.ear</u> (or the value specified in <u>IWSWAR</u> - <u>Name of Inbound Web Services WAR</u> setting) and to be deployed into Oracle WebLogic. This step is optional if configuration overrides are in use.

Note: For customers who want to use manual deployment methods, use the <u>iwsdeploy.sh -b</u> option to prevent autodeploy. See <u>iwsdeploy - Inbound Web Services Deployment</u> for details.

At this point, the product web services are ready for deployment into the JEE web application server.

5.5.5 Inbound Web Services Deployment Process

After the build of the inbound web services EAR is complete (as outlined in <u>Inbound Web Services</u> <u>Configuration Process</u>) the final step to implement your application is to deploy the product within the JEE web application server.

There are three methods of deploying the product within the JEE web application server:

- Use the deployment utilities provided on the console of the JEE web application server. The EAR
 files are available under \$SPLEBASE/splapp/iws/gen can be manually deployed using the
 console. Refer to the Oracle Revenue Management and Billing Installation Guide for specific
 platform instructions and the administration guide for the JEE web application server.
- Use the deployment utilities provided on the command line of the JEE web application server. The
 EAR files are available under \$SPLEBASE/splapp/iws/gen can be manually deployed using the JEE
 web application server vendor supplied deployment command line utilities. Refer to the Oracle
 Revenue Management and Billing Installation Guide for specific platform instructions and the
 administration guide for the JEE web application server.
- Use the <u>iwsdeploy</u> utility for command line access for deployment. See <u>iwsdeploy Inbound Web</u>
 Services Deployment for details.
- Use the inbound web services online transaction

Several specific utilities from Oracle WebLogic are provided with the Oracle Utilities Application Framework applications to deploy the web application to the domain.




Figure 28: Inbound Web Services Deployment Process

5.5.6 Quick Reference Guide for Inbound Web Services Configuration

Use the following Quick Reference Guides to identify which process should be used to make configuration changes to the IWS component of Oracle Revenue Management and Billing:

- If the change is to any setting contained in the <u>ENVIRON.INI</u> for the IWS then you must run the following utilities in the order indicated:
 - 1. Execute the <u>configureEnv</u> utility to reflect the parameter change in the <u>ENVIRON.INI</u>. See <u>configureEnv</u> Set up Environment Settings for details.
 - 2. Execute the <u>initialSetup</u> utility (with the -t option) to rebuild the configuration files using the <u>ENVIRON.INI</u> and provided template files. This will reset the configuration to the contents of the base template files or <u>custom template</u> (if used). See <u>initialSetup Maintain Configuration Settings</u> and <u>Implementing Custom Templates</u> for more information.
 - Any configuration changes that are overridden by templates (base or <u>custom template</u>)
 must be manually reapplied (if necessary). See <u>Implementing Custom Templates</u> for
 details.
 - 4. Execute the <u>initialSetup</u> utility (with the -w option) to implement the configuration files in the product IWS files. This step is not necessary if you are using <u>configuration overrides</u>. See <u>initialSetup Maintain Configuration Settings</u> and <u>Implementing Custom Templates</u> for more information.
 - 5. Execute the <u>iwsdeploy</u> utility to build and deploy. See <u>iwsdeploy Inbound Web Services</u>

 <u>Deployment</u> for details.
- If the change is to any setting not contained in the <u>ENVIRON.INI</u> for the IWS but is in the configuration files for the IWS then you must run the following utilities in the order indicated:
 - 1. Make any manual changes to the relevant configuration files.
 - 2. Execute the <u>initialSetup</u>, with the **-w** option, utility to implement the configuration files in the product IWS files. See <u>initialSetup</u> <u>Maintain Configuration Settings</u> for details.

5.5.7 Inbound Web Services Deployment Utilities

After the configuration of the inbound web services is complete (as outlined in <u>Inbound Web Services</u> <u>Configuration Process</u>) the final step to implement your application is to deploy the product within Oracle WebLogic.

There are three methods of deploying the inbound web services component within the JEE web application server:

An inbound web services Deployment facility available from the product online. This is accessible from the Admin → I → Inbound Web Services Deployment menu item. This is suitable for development environments only. For example:




Figure 29: Inbound Web Services Online Transaction

- Use the <u>iwsdeploy</u> utility to trigger a deployment from the command line. See <u>iwsdeploy</u> –
 Inbound Web Services Deployment for details.
- Execute the <u>iwsdeploy</u> utility but manually deploy the web services EAR file to the server(s) or cluster using the Oracle WebLogic console or deployment utilities. See <u>iwsdeploy – Inbound Web</u> Services Deployment for details.

5.6 Batch Server Configuration

The batch component contains several configuration files and utilities to manage the configuration of the cluster, threadpools and submitters. This section outlines the configuration files and configuration process for configuring batch.

5.6.1 Batch Configuration Files

As with the online component of the Oracle Utilities Application Framework there are a number of configuration files that control the performance and behaviour of the batch component.

The batch component houses the configuration files differently to the online and web services component. The online and web services are housed within a JEE web application server and therefore the configuration files are located according to the JEE standards.

In the batch component the configuration is housed in directories as the batch component is housed as a standalone process that is clustered using Oracle Coherence. Therefore, during the configuration process, the configuration files used by the batch component are built using templates using the initialSetup utility. This utility deposits the configuration files in the \$SPLEBASE\splapp\standalone\config directory. See initialSetup — Maintain Configuration Settings for details.

The figure below summarizes the directory structure and the relevant configuration files:




Figure 30: Batch Configuration Files

The following configuration files (along with their templates) are listed below:

Configuration File	Contents
e0Batch.properties – General Batch Properties	General environment settings
<u>hibernate.properties – Database Connectivity</u> <u>Settings</u>	Database connectivity
log4j2.properties – Product Logging Configuration	Logging settings submitjob login settings threadpoolworker login settings
spl.properties - Product Behaviour Settings	Application behaviour
<u>submitbatch.properties</u> – <u>Submitter</u> <u>Configuration (BATCH)</u>	submitjob default settings
threadpoolworker.properties – Threadpool Configuration (BATCH)	threadpoolworker configuration
<u>coherence-cache-config.xml - Oracle</u> <u>Coherence Configuration (BATCH)</u>	Cache settings for cluster
tangosol-coherence-override.xml - Coherence Overrides (BATCH)	Override setting for cluster

5.6.2 General Configuration Process

To configure the batch component during the installation process and post-installation then the following process should be used:




Figure 31: Batch Configuration Process

• The <u>configureEnv</u> utility is used during installation time and can be used post installation to set parameters in the <u>ENVIRON.INI</u>. See <u>configureEnv – Set up Environment Settings</u> for details.

Note: The <u>configureEnv</u> utility should be used to make any changes to the <u>ENVIRON.INI</u>. Manual changes to this configuration file are not recommended.

• After the ENVIRON.INI has been set or altered, the settings must be reflected in the relevant configuration files used by the batch component using the initialSetup utility. The initialSetup utility takes the relevant templates, builds the configuration files and deposits them in the SPLEBASE\splapp\standalone\config directory. See initialSetup — Maintain Configuration Settings for details.

The configuration files are now ready to be used for the batch component. Additional configuration can be performed using <u>bedit</u>. See <u>Configuring Batch Using Bedit</u> for details.

5.6.3 Configuring Batch Using Bedit

The <u>bedit – Batch Edit</u> utility is a set of wizards that allow a batch configuration to be built for an implementation using simple commands. The utility uses a set of templates to build a complete set of configuration files for the cluster, its threadpools and submitters at a global and individual level.

For guidelines and scenarios using this facility, refer to the <u>Batch Best Practices</u> (Document ID: 836362.1) reference paper available from My Oracle Support.

5.6.3.1 Batch Configuration Overview Using Bedit

The bedit utility allows for a set of configuration files to be built on top of the global configuration setting managed using the <u>Batch Configuration Guidelines</u>. The following process should be used:

- **Global Settings** Specify global batch settings using the <u>configureEnv</u> utility to set the defaults in the ENVIRON.INI. See <u>configureEnv</u> Set up Environment Settings for details.
- **Apply Settings** Apply any configuration settings to the global templates and default configuration files using the <u>initialSetup</u> utility. See <u>initialSetup</u> <u>Maintain Configuration Settings</u> for details.

Note: Use the -t option to allow templates to be rebuilt only. Using other options may affect online.

- Perform Cluster Configuration Configure the desired <u>cluster configuration</u> using <u>bedit</u>. Clusters are set up once, per environment either using multicast, unicast or single server optimized configurations. See <u>Cluster Configuration using bedit</u> for details.
- Perform Threadpoolworker Configuration Configure the desired <u>threadpoolworker configuration</u> using <u>bedit</u>. Threadpoolworkers can be created on an individual basis with unique configurations or labelled to share configurations. See <u>Threadpoolworker Configuration Using Bedit for details</u>.
- Perform Submitter Configuration Configure the desired <u>submitter configuration</u> using <u>bedit</u>.
 Submitters can be set up for specific development execution modes (THIN or LOCAL), generic configuration or project specific jobs. See <u>Submitter Configuration using bedit</u> for details.

The process is shown below:




Figure 32: bedit Configuration Process

Note: At any time, the file name and location of the generated file is determined at the start of the edit session or using the what command.

5.6.3.2 Batch Edit Usage Guidelines

The <u>bedit</u> utility is available to simplify the creation and maintenance of these files to promote stability and flexibility whilst minimizing maintenance mistakes (see <u>bedit - Batch Edit</u> for details). The following guidelines apply when using the utility:

- The command line options specify the configuration file to be modified. The specific configuration file or the shortcut option can be used to set the scope of the command.
- Pre-optimized specialist templates (with .be extension) are used to decide the parameters
 applicable to the setting or command used in the configuration file being edited. The template
 name is displayed at the start of execution to confirm the configuration file edited.
- Configuration settings can be added, modified, or deleted using interactive commands. The following commands are supported:

Command	Usage
add <group></group>	Add a group <group></group> with all its sub-elements. Values for the variables are defaulted from the template.
del <group></group>	Delete the group <group> and all its sub-elements.</group>
exit	Exit the editor. If changes have been made, confirmation may be required.
help <topic></topic>	Show online help for command or setting. Without a topic a list of topics for the configuration file and commands are listed
save	Save any changes to the configuration file
set <var> <value></value></var>	This command to update a variable's <var></var> to value <value></value> . If there are multiple sub-elements for a group, the variable name must be fully qualified by its parent group(s) - e.g., set pool.2 poolname DEFAULT . If there is only one group, the variable does not need to be qualified - e.g., set poolname DEFAULT .
what	This command shows which file is being edited and the template on which it is based.

- The templates will generate the necessary settings based upon the scope of the command. Use the online help to determine valid settings for your configuration.
- User preferences for labels and cluster types are stored in the be.prefs file.
- Using the save command will reflect your changes to the configuration file directly.
- If exit command is issued and changes have been detected, then a confirmation message will be issued. Press y to save, n to quit without saving or c to cancel out of exit command.
- Each subsection will outline specific settings within the scope of each configuration.

5.6.3.3 Cluster Configuration Using bedit

Oracle Coherence is used to define and manage the batch cluster. The cluster must be configured to decide how the cluster will operate on the network and the scope of the cluster. The major decision for this step in the process is the type of cluster to implement. There are three styles of cluster supported:

- Multicast cluster (default) A batch cluster based upon the multicast network protocol. The
 protocol requires a multicast address and common port. This protocol supports dynamic
 clustering.
- Unicast cluster A batch cluster based upon unicast network protocol. Each host and port in the cluster must be explicitly configured.
- **Single Server cluster** A batch cluster confined to a single server using unicast. This is designed for use in non-production environments to simplify the configuration.

The templates for these cluster types are as follows:

Template	Usage
tangosol-coherence-override.mc.be	Multicast cluster
tangosol-coherence-override.ss.be	Single Server cluster (useful for non-production environments)
tangosol-coherence-override.wka.be	Unicast (or wka) cluster

To configure the cluster use one of the example commands:

Commands	Description
bedit.sh -c -t <type></type>	Create or edit Cluster configuration. The -t option is used to set the cluster type as specified (mc - Multicast, wka - Unicast or ss - Single Server). Specifying the -t option on an already defined cluster may change the type.
bedit.sh -c	Maintain the cluster configuration. Cluster type is defaulted from be.prefs.
bedit.sh tangosol-coherence-override.xml	Edit the tangosol-coherence-override.xml file.

Once the configuration is opened the following settings need to be configured:

Variable	SS	wka	mc	Recommendations
cluster				Unique cluster name for environment. This must be unique for the cluster. Typically use the environment name or database name.
address	•	•	•	IP address or host name for this node in the cluster. Use localhost if possible, to minimize maintenance across hosts.

Variable	ss	wka	mc	Recommendations
port	•	•	•	Unique port used for cluster. This must be unique per cluster per host. Its use will vary from cluster type to cluster type. Refer to the online help for more information.
loglevel	•	•	•	The logging level associated with cluster operations. Refer to the online help to decide the amount of information you wish to log. The higher the value the more that is logged. High values are used by developers typically.
mode	•	•	•	The Coherence mode that the cluster is to be scoped to. Refer to the online help for more information.
socket		•		This is a section for each of the hosts in the Well-Known Address format. Each host is a separate socket entry. Refer to the online help for more information.
wkaaddress		•		The IP address or host name of the member of the cluster assigned to this socket.
wkaport				The port number assigned of the member of the cluster assigned to this socket. This value ideally is the same across all hosts in the cluster but can be overridden to overcome port conflicts. The port number on each node must match the number assigned to the port value.

For unicast implementations a socket section must be created per host/port combination defined in the file using the following commands:

• Use the add socket command to add a new socket group. The group name generated will be in the form socket.<number> where <number> is the sequence number. For example:

```
> add socket
...
socket.2
wkaaddress (localhost)
wkaport (42020)
```

Set the wkaaddress and wkaport using the set socket.
 variable> <value> where
 set the wkaaddress and wkaport using the set socket.
 set the wkaaddress or wkaport and socket.
 set the wkaport and socket.
 set the

```
> set socket.2 wkaport 6402
...
socket.2
wkaaddress (localhost)
wkaport (6402)
```

• Repeat for each node in the cluster.

5.6.3.4 Socket Issues in CLUSTERED Mode

To help minimization of packet loss, the operating socket buffers need to be large enough to handle the incoming network traffic while your Java application is paused during garbage collection. By default, Oracle Coherence will attempt to allocate a socket buffer of 2MB. If your operating system is not configured to allow for large buffers, Oracle Coherence will utilize smaller buffers. Most versions of UNIX use a very low default buffer limit, which should be increased to at least 2MB.

Starting with Oracle Coherence 3.1, you would receive the following warning if the operating system failed to allocate the full size buffer.

UnicastUdpSocket failed to set receive buffer size to 1428 packets (2096304 bytes); actual size is 89 packets (131071 bytes). Consult your OS documentation regarding increasing the maximum socket buffer size. Proceeding with the actual value may cause sub-optimal performance.

Though it is safe to operate with the smaller buffers, it is recommended that you configure your OS to allow for larger buffers as mentioned in the below table.

Clustering Mode	Configuration Settings
Linux	sysctl -w net.core.rmem_max=2097152
	sysctl -w net.core.wmem_max=2097152
AIX	no -o rfc1323=1
	no -o sb_max=4194304
Windows	Windows does not impose a buffer size restriction by default.

5.6.3.5 Threadpoolworker Configuration Using Bedit

Once a cluster is defined the threadpools that will execute across that cluster must be defined with their name and attributes. Oracle Utilities Application Framework applications supports different types of threadpools that can execute batch processes with the following:

- Cache Threadpools Threadpoolworkers that do not execute jobs but act as co-ordination node
 for network traffic. It is recommended that there be at least one cache threadpool per physical
 host per cluster. For a discussion of cache threadpools, refer to the <u>Batch Best Practices</u> (Document
 ID: 836362.1) reference paper available from <u>My Oracle Support</u>. This threadpool type has
 tangosol.coherence.distributed.localstorage set to true.
- **Job Threadpools** Threadpoolworkers that are optimized to run batch threads with support for additional java options and other cluster specific optimization settings.
- **Default Threadpools** For backward compatibility, the default template used is pre-optimized with settings from past releases. It is recommended to migrate from this template to job template.

The templates for these threadpool types are as follows:

Template	Usage
threadpoolworker.be.template	Default template

Template	Usage
threadpoolworker.cache.be.template	Cache Threadpool template
threadpoolworker.job.be.template	Job Threadpool templates

• To configure the cluster use one of the example commands:

Commands	Description
bedit.sh -w -l <type></type>	Create or edit threadpool configuration. The -1 option is used to set the label type as specified (cache - cache or job - Job).
bedit.sh -w	Maintain the default threadpool configuration.
bedit.sh threadpoolworker.properties	Edit the threadpoolworker.properties file.

• Once the configuration is opened the following settings need to be configured:

Parameter	Recommendations
minheap	Minimum JVM Heap size
maxheap	Maximum JVM Heap size
maxperm	Maximum JVM permgen size
daemon	Whether the threadpool should run the online submission daemon. This value should be set to false for production environments.
dkidisabled	Key insert behavior
storage	Whether local storage is enabled. Used for cache threadpools.
distthds	Number of internal threads used for cache threadpools.
invocthds	Number of internal threads used for invocation services.
role	Information role for the threadpools used for monitoring
jmxstartport	JMX Start Port
pool	Group section for each threadpool
poolname	Name of threadpool
threads	Maximum number of threads for the threadpool per instance

For multiple threadpools per configuration use the following process:

• Use the add pool command to add a new pool group. The group name generated will be in the form pool.<number> where <number> is the sequence number. For example:

```
> add pool
...
pool.2
wkaaddress (localhost)
wkaport (42020)
```

Set the poolname and threads using the set pool.
 roumber> <variable> <value> where <number> is the sequence number, <variable> is poolname or threads and <value> is the desired value.

5.6.3.6 Submitter Configuration using Bedit

The last step in configuration is to configure the submitters. A submitter is a JVM that submits jobs or threads of jobs to a threadpoolworker and waits for the thread to complete. It is responsible for interfacing to the threadpoolworker and also provides an interface to the process that submits the jobs in the first place (e.g., a third party batch scheduler or Oracle Scheduler).

A submitter needs one or more of the following pieces of information:

- It needs a configuration file that defines the parameters to be used for the individual batch process being executed. These can be global configuration files or individual configuration files optimized for a batch process.
- Command line options to set or override configuration parameters that define the execution parameters for the individual process or thread.

The single execution of a submitter can run a single threaded batch job, a single individual thread of a multi-threaded batch job or all threads of a multi-threaded job.

To create a specific configuration file for a batch job any of the following commands can be used:

Commands	Description
bedit.sh -l <type></type>	Create or edit submitter configuration. The -I option is used to set the label type for development purposes as specified (THIN - THIN mode or LOCAL- local mode).
bedit.sh -b <batch_cd></batch_cd>	Create or edit submitter configuration for job batch_cd>.
bedit.sh -s	Edit default submitter configuration

• Once the configuration is opened the following settings need to be configured:

Parameter	Recommendations
poolname	Name of threadpool to execute this submitter within
threads	Thread limit of submitter. The number of threads must be equal to or less than the number of threads allocated to executing instances of the threadpool
commit	Default commit interval. This overrides the commit interval defined internally for the batch job.
user	The User ID defined to the User record, to be used to determine execution permissions and is used for records updated and created by this process. This MUST be a valid defined used.
lang	The language pack used for the batch process (default is ENG)
storage	This sets whether this node is a storage node. Used for submitters that use THIN mode (for developers). This value is recommended to be set to false for all other submitter types.

Parameter	Recommendations
role	The role used for this submitter. This is used for the JMX monitoring interface as a filter. By default, the batch code used for this value.
soft	Group section for soft parameters. One section per parameter
parm	Parameter name as outlined on Batch Control.
value	Value assigned to the parameter

For multiple parameters per configuration use the following process:

• Use the add soft command to add a new parameter group. The group name generated will be in the form soft.<number> where <number> is the sequence number. For example:

```
> add soft
...
soft.2
  parm (maxErrors)
  value (500)
```

• Set the parm and value using the set pool.<number> <variable> <value> where <number> is the sequence number, <variable> is parm or value and <value> is the desired value. For example:

```
> set soft.2 parm fred
...
soft.2
parm (fred)
value (500)
```

5.6.4 Batch Configuration Guidelines

The following sections outline general guidelines for batch configuration.

5.6.4.1 Cache Threadpools

One of the new facilities in the batch architecture is the ability to define cache or storage nodes in your architecture. By default, a batch cluster communicates across the cluster elements such as threadpools the state of other elements in the cluster. While this has benefits, as any element in the cluster can be queried, through JMX, to find out the global status of all active processes in that cluster, it can generate a large amount of network traffic and cause instability as the cluster is performing a large amount of maintenance operations. To address this, your application now allows you to create cache or storage threadpools. These act as conduits with the architecture and greatly reduce the network traffic and overheads in managing the cluster. This translates to more stable clusters.

Cluster Cluster Threadpool Threadpool Threadpool Threadpool Instance Instance Instance Instance Cache Threadpool Threadpool Threadpool Threadpool Threadpool Instance Instance Instance Instance With Cache Without Cache

The communications between elements are shown below:

Figure 33: Cache Architecture

The performance advantages of the cache increases with the number of elements the cluster must manage and cache threadpools have the following implementation recommendations:

- Cache threadpools do not execute any threads of any jobs within them. They are exclusively used for administration, a storage node for the cluster state and a conduit for cluster management.
- Cache threadpools act as Coherence local storage nodes to maintain the integrity of the cluster and allow cluster management.
- Cache threadpools are ideally suited to allow JMX connections to monitor the performance of the cluster using the Batch JMX Reference interface.
- At least one cache threadpool per cluster per host is recommended. Multiple cache threadpools
 can be implemented where high availability is required or there are number of submitters, threads
 and/or threadpools to manage.
- If a cache threadpool is shut down and no cache threadpools are active at any time, the cluster will not revert to individual elements communicating across other elements.
- To create cache clusters, use the <u>bedit.sh</u>-I cache command. A prebuilt template is created for the
 cache where <u>storage</u> is enabled, <u>distthds</u>, <u>invocthds</u> and the number of threads is set to 0 (to
 prevent jobs from running in the cache). See <u>bedit Batch Edit</u> for details.

5.6.4.2 Adding Custom JMX Information to Jobs

The <u>Batch Server JMX interface</u> can be extended for additional tags using a new parameter f1.jmxInfo for filtering purposes or additional documentation. For example:




Figure 34: JMXInfo in jconsole

The submitbatch.properties file for a particular job should have the following additional parameter:

com.splwg.batch.submitter.softParameter.f1.jmxInfo.<tag>=<value>

where:

Command Line Option	Description
<tag></tag>	Additional JMX information identifier
<value></value>	Value for parameter

Multiple parameters of this type are supported within a single configuration file.

For example:

com.splwg.batch.submitter.softParameter.f1.jmxInfo.foo=bar

When using bedit the command sequence to use this facility is:

- Add a soft parameter section for each desired tag/value pair using the command (a section soft.<sequence> is created where <sequence> is a generated sequence number):
- Specify the parm property as f1.jmxlnfo.<tag> where <tag> is the desired tag using the command: set soft.<sequence> parm f1.jmxlnfo.<tag>
- Specify the value property as the desired value for the tag using the command: set soft.<sequence> value <value>

It is possible to specify this setting on the $\underline{\text{submitjob.sh}}$ command using the -x option (see $\underline{\text{submitjob.sh}}$ Command using the -x option (see $\underline{\text{submitjob.sh}}$). For example:

```
submit.sh ... -x f1.jmxInfo.foo=bar
```

5.6.5 Batch Performance

To improve the batch job performance, we recommend you set the following properties in the custom spl.properties template:

- com.oracle.ouaf.batch.quickEndOfThreadUpdatesDisabled=false
- com.oracle.ouaf.batch.enableDBsequence=true
- com.oracle.ouaf.javaCobolTransitionFlushRequired=false

Points to Note:

Before you set the value of the com.oracle.ouaf.batch.enableDBsequence parameter to true, you need to do the following:

1. Create the following sequence in the database using the administrator's credentials:

2. Execute the Oragensec utility.

5.7 Oracle Cloud Support

The Oracle Utilities products are progressively being implemented on Oracle Cloud in both Software as a Service (SaaS) and Platform as a Service (PaaS). This has resulted in new cloud-based configurations and features. These features are also available for customers with customers with on premise and hybrid implementations. This section will outline the additional configuration facilities that can be used for on premise implementations.

5.7.1 Support for Host Allow Listing

The hosts and port numbers used by the feature sets in the ORMB application are typically restricted in scope for on premise products but on the cloud, the ports and hosts can be restricted to ensure compliance. The product supports the configuration of the hosts and ports, which are accessible from the online system can be specified in an allow list which is validated at configuration time and runtime.

Note: URL's within configuration files are subject to deployment restrictions within the deployment facility itself.

Oracle Utilities Application Framework applications now support allow listing of URIs with schemes such as t3, t3s, ldap, ldaps, jdbc, etc. URI allow listing can be enabled by setting the com.oracle.ouaf.uriValidation.enable parameter in the spl.properties file to true. Once enabled, it is possible to limit the values of URL's within the product for key objects with the configuration. This is implemented as an allow list that can filter on scheme (aka protocol), hosts and ports. These are checked at runtime and can generate an error if they do not adhere to the allow list.

The feature allows for the following:

- Individual scheme, hosts and port combinations can be configured to limit runtime access for specific features.
- Specification of the '*' wildcard is supported for scheme, hosts, and ports.

Note: Custom allowlists are not supported on Oracle Utilities SaaS Cloud Services.

There are several configuration settings (ENVIRON.INI) that control the allow list:

- <u>CLOUD RESTRICTION URLS ENABLE</u> Whether the allow listing feature is used or not (default is false). See <u>com.oracle.ouaf.web.allowCORS</u> <u>Enable Cross Origin Resource Sharing for details</u>.
- <u>CLOUD WHITE LIST PATH</u> The full path to the allow list file for Oracle Cloud. This variable should
 not be populated for on premise implementations. This is only used if
 <u>CLOUD RESTRICTION URLS ENABLE</u> is set to <u>true</u>. See <u>com.oracle.ouaf.whitelist.file</u> <u>Oracle URL</u>
 Allow List Filename and Location for details.
- <u>CLOUD CUSTOM WHITE LIST PATH</u> The full path to a custom allowlist for Oracle Cloud or on premise implementations. This is only used if <u>CLOUD RESTRICTION URLS ENABLE</u> is set to <u>true</u>.
 See com.oracle.ouaf.customer.whitelist.file Customer's URL Allow List File for details.

The format of the allow list is an XML format document:

Attribute	Description
<uri></uri>	URI tag

Attribute	Description
<path></path>	Specific path on the host.
<host></host>	Host name or IP Address for host. Wildcards are supported. IPV4 and IPV6 formats are supported.
<port></port>	Port Number. Wildcards are supported.
<scheme></scheme>	Protocol supported (HTTP or HTTPS support). Wildcards are supported.

For example:

There must be a separate entry for each host, path, port, and scheme combination. Oracle Utilities Application Framework applications now supports allow listing of URIs with schemes such as t3, t3s, ldap, ldaps, jdbc, etc.

The table below indicates when validation is performed for the following components:

Component	Design-Time Validation	Run-Time Validation
Message Sender Context	•	
JNDI Server	•	
Web Service Adapter	•	
Feature Configuration	•	
Reporting Options	•	
External Navigation Keys	•	
HTTP Sender		
Real Time HTTP Sender		
JSON Sender		

Component	Design-Time Validation	Run-Time Validation
Real Time Email Sender		
JMS Sender		
SMS BPEL Sender		
Web Services (WSDL, OPA etc)		

5.7.2 Support for URI Specification Using Substitution Variables

Applications need to define URI links to the integrate components for seamless navigation to different application pages, for map viewer, etc. URI specifications can now include substitution variables to allow parameterization of URI components.

This new enhancement featuring substitution variables ensures support for secure, stable, and uniformly configured environments. For configuration stability such URL values will be defined using substitution variables, aka aliases. E.g., "@CCB@/demoprop/cis.jsp". This would help in migrating values between different environments, e.g., from CCB Test to CCB Prod environment, and in performing CMA extracts that would allow to pull URL values that are not environment specific.

A substitution list is provided to implement the physical path per environment. This file is maintained in \$SPLEBASE/etc/substitutionVariableList.xml.

The substitution list file can be specified using the CLOUD_SUBSTITUTION_VARIABLE_LIST_FILE_LOCATION config parameter in the ENVIRON.INI file.

Following is the format of the substitution variables file:

</substitutionVariables>

Attribute	Description
<urivariable></urivariable>	URI Variable tag
<name></name>	The name of the substitution variable.
<value></value>	The URI (URL/Path) of the substitution variable.

uriVariable element has the attribute "allURIChildComponentsAreValid" with allowed values being true or false. If the attribute value is set to false, then the uriVariable value needs to be verified against the white list after the variable is replaced with the actual value. If the allURIChildComponentsAreValid is set to true, or is omitted, then this indicates that the variable value is already white listed and there is no further validation of the uri and all its child components (such as path, query, and fragement) is needed.

Note: The default behavior is true.

The URI specification feature automatically includes the variable **SPLOUTPUT**. This is a system variable commonly defined with a valid file path that implementations may write files to. Automatically providing the configuration for this variable provides backward compatibility for any code that supported referencing "@SPLOUTPUT@" for a file location. The SPLOUTPUT variable is automatically identified and substituted without having to explicitly define it in the substitution variable XML file.

```
For example,
```

The following substitution variables are provided by default in OUAF:

- 1. F1_CMA_FILES
- F1_BASE_REST_URL
- 3. F1_BASE_IWS_URI
- 4. F1_BASE_WEB_URI
- CPS FRAME ANS HOST1
- 6. CPS FRAME ANS HOST2

Note: For CORS if more than 2 frame ancestors are needed, add additional substitution variables. Example: CSP_FRAME_ANS_HOST3.

- 7. FA DOMAIN
- 8. ALM_DOMAIN

9. F1_OPEN_API_BASE_URL

Note: The below substitution variables are also provided by default, but no product functionality is using them. In a future release, these variables will no longer be delivered (to remove any ambiguity). Implementation teams are suggested not to use any of the below names, but should rather use CM variable names.

- 10. F1 BI EXTRACTS
- 11. F1 INTERNAL FILES
- 12. F1_CUST_APP_BASE
- 13. F1 PROCESS DIR
- 14. F1_SVC_CATALOG_WSDL_DIR
- 15. F1_PDB_EXTRACTS

Points to Note: The list must not contain variables and file paths that contain internal product infrastructure. For example, config files, binaries, properties, security info and others.

The list must not contain existing environment variables such as SPLEBASE, COBOL_RUNTIME_LIB, APPVIEWER DIR and their corresponding application directories.

5.7.3 Defining File Alias Using Extendable Lookup

In addition to the above-mentioned support for URI specification using substitution variables, an alternate option has been provided that allows for defining native file storage locations using an extendable lookup. The F1-FileStorage (File Storage Configuration) extendable lookup has been provided. Using this extendable lookup, a value may be defined referencing the "Native File Storage" file adapter option and then defining the file path that this value represents. The file path field follows the same rules as any other file path. For example, it can reference "@SPLOUTPUT@" or any other value defined in the Substitution Variables properties file. In addition, if the system has been configured to validate the value against an allow list, this is also enforced.

A new syntax has been defined for referencing file locations during configuration, for example in "File Path" parameters for a batch control: file-storage://{ExtendableLookupValue}.

Refer to the online help for more information about the supported syntax.

5.7.4 Support for Oracle Cloud Storage Access

The system has been enhanced to allow code that reads or writes files to reference an Oracle Cloud Storage location (container) rather than the native file system. The extendable lookup F1-FileStorage (File Storage Configuration) has been provided to support this. Using this extendable lookup, a value may be defined referencing the "Oracle Cloud Object Storage" file adapter option.

With that configuration, your implementation may define the REST Endpoint URL, user name and password for accessing the storage location. Using this configuration, the same syntax described above may then be used when defining a File Path in the application, for example a parameter for a batch control.

file-storage://{ExtendableLookupValue}/{serviceName}

Refer to the online help for more information about the supported syntax.

5.7.5 Consolidated Logging

Note: This feature only applies to the clustered environments of your application.

Utilities products provisioned on the cloud would be hosted across multiple cluster nodes. The Application server or the inbound web services could be spread across multiple nodes making their corresponding logs, distributed. In order to debug or to monitor the application components, users are provided with a consolidated view of these distributed logs. Oracle Utilities Application Framework leverages RSysLog to accomplish the task to consolidate the distributed logs.

Note: The configuration and usage of RSysLog is not covered in this document.

Users can configure the location of the distributed logs using the com.oracle.ouaf.consolidatedLog.fileName parameter in the spl.properties file. If configured, the consolidated logs would be picked up from the specified logs file and displayed to the user. The RSysLog should be configured to retrieve the distributed logs and consolidate them into the log file specified against the com.oracle.ouaf.consolidatedLog.fileName property.

5.7.6 Diagnostics Support (WLDF)

Points to Note:

This feature only applies to Oracle WebLogic 12 and above implementations only.

Refer to the Configuring and Capturing Diagnostic Images for additional advice.

Oracle WebLogic includes a diagnostics capability in the form of <u>Oracle WebLogic Diagnostics Framework</u> (WLDF). Typically, most diagnostics tools only detect an issue after it has happened, which means important diagnostic information may not be captured. The WLDF captures information at the time of the issue and after to provide additional diagnostics in a standard format for inclusion in diagnostic tools built into Oracle products and for Service Requests within <u>My Oracle Support</u>.

The diagnostic engines work in the following way:

- The diagnostics facility is enabled to capture information. As part of that enablement the location of the diagnostics is configured.
- A set of rules are added to configure the diagnostics engine to recognize issues that are above and beyond the typical issues. WLDF detects common java issues automatically.
- When a rule or the diagnostic engine detects an error is occurring or has occurred, it gathers as
 much diagnostics information it can at the time of the error and creates a diagnostic image which
 assembles the diagnostics information into a structured format. This is placed in the configured
 location.
- Diagnostic images are available from the console as well as Oracle Enterprise Manager where they
 can be viewed, analyzed, and attached to Service Requests as necessary.

Oracle Utilities Application Framework applications now supports the WLDF using the following:

A set of configuration settings that enable the support as well as set some basic settings. These
settings are primarily used for embedded installations. For native installations, the WLDF
definitions are included in the provided <u>Domain Templates</u>.

Note: For customers with pre-existing native installations wanting to use this facility, it is recommended to enable the facility in an embedded installation and manually make the changes to your domain to match the settings using the Oracle WebLogic console or Oracle Fusion Middleware console.

• A set of base rules to instruct WLDF the conditions to track and detach issues. These are customizable rules for Oracle WebLogic to detect any issues outside of typical issues.

The following parameter controls the implementation of the Diagnostics Framework:

 WLS DIAGNOSTIC CONTEXT ENABLED - This enables (true) or disables (false) the diagnostics generation support in the product. See <u>WLS_DIAGNOSTIC_CONTEXT_ENABLED - ECID Support</u> for details.

For native installations, the following process should be used from the Oracle WebLogic console to enable support:

- 1. Navigate to the Environment → Servers menu item and click on the product server name to enable.
- 2. In the Configuration tab, change the value of Diagnostic Volume to the desired level of diagnostics. It is recommended to use Low as a minimum. Save the changes and repeat for each product server (if multiple instances are implemented in the domain).
- 3. Navigate to the Diagnostics → Built-in Diagnostics Modules menu item and select the product servers. Click on the Activate button to enable basic diagnostics. This should change the Status to Active.
- 4. If a custom Diagnostic Module is to be used, then navigate to the Diagnostics → Diagnostic Modules menu item and select the desired diagnostic module to maintain. From the Targets tab, select the product servers to apply the desired diagnostics module. Save the changes.

5.7.6.1 ECID Support

Note: This feature only applies to Oracle WebLogic 12 and above implementations only.

Oracle WebLogic includes a set of facilities to add additional information to transactions known as the <u>Execution Context Identifier (ECID)</u>. The single ECID is attached to each unique transaction within the ORMB application. This allows diagnostic tools to perform forensic analysis based on the identifier across the architecture. There are a set of rules that apply to the ECID within the ORMB application:

- A unique ECID is generated at the start of a transaction within the product. This ECID is active for all calls within the product till a COMMIT or ROLLBACK is issued by the product. This constitutes a transaction boundary within the product.
- The ECID is only generated for online web-based transactions in the present release.
- The ECID is used within the logs, diagnostic images and transaction tracking facilities within Oracle WebLogic and the related database connections.
- The use of ECID is optional and disabled, by default, for backward compatibility.
- The ECID is used by the various Oracle diagnostics tools such as <u>Oracle Enterprise Manager</u>, <u>JVMD</u> and <u>Business Transaction Management</u>.

Note: This is only supported when using Oracle WebLogic JDBC Data Sources. It is not supported for UCP at the present time.

The following parameters control the implementation of the Diagnostics Framework:

- WLS_DIAGNOSTIC_CONTEXT_ENABLED This enables (true) or disables (false) the diagnostics generation support in the product. See WLS_DIAGNOSTIC_CONTEXT_ENABLED ECID Support for details.
- For native installations, the following process should be used from the Oracle WebLogic console to enable support:
- Navigate to the Diagnostics → Context menu item.
- Select the product servers and click on Enable to enable ECID support.
- The status of the selected servers should change to Enabled.

5.7.7 Global Cache Flush Support

One of the architectural features of Oracle Utilities Application Framework applications is the support for caching of commonly used data. This cache is used to prevent the transactions to perform unnecessary calls for commonly used data. This cache is loaded and maintained by the product automatically.

In some cases, it may be necessary to force a refresh of the cache to reload the static data. Whilst a number of utilities are provided to <u>flush the online/web services</u> cache as well as the <u>batch cache</u>, if there were a number of servers or threadpools then the cache request may have to be performed on each threadpool or server.

In the current release any cache request can be configured to flush all caches, known as a global flush, across the architecture. Use of this facility is optional, but recommended in production environments to ensure consistent processing.

To use this facility the following must be configured:

- The <u>ouaf.flush.jms.disabled</u> property in the <u>spl.properties</u> file must be set to false. See ouaf.flush.jms.disabled Global Flush Supported for details.
- The <u>ouaf.flush.jms.connection</u>, <u>ouaf.flush.jms.requestTopic</u> and <u>ouaf.flush.jms.responseTopic</u> properties must be populated in the <u>spl.properties</u> with the JMS resources used. These JMS resources must be created within the domain of the product. See <u>ouaf.flush.jms.connection</u> <u>Connection Factory for Global Flush</u>, <u>ouaf.flush.jms.requestTopic</u> <u>Global Flush Request Topic</u> and <u>ouaf.flush.jms.responseTopic</u> <u>Global Flush Response Topic</u>.

Once enabled all flush requests now are global.

The global flush operates in the following way:

- When a flush is requested from the online using the JSP or JMX facility, Web Services through JMX and batch run through F1-FLUSH, an entry is placed in the JMS Topic dictated by ouaf.flush.jms.requestTopic Global Flush Request Topic.
- Each of the components of the architecture has subscribed to the JMS resource specified by <u>ouaf.flush.jms.requestTopic – Global Flush Request Topic</u> at their startup time.
- When they receive a message in that topic, each component flushes their cache according to their local methods and sends an appropriate response in the JMS resource specified by ouaf.flush.jms.responseTopic Global Flush Response Topic indicating success or failure. This JMS resource may be monitored using the Oracle WebLogic console, Oracle Enterprise Manager, a JMS Browser or the JMS Viewing facility within the product.

Note: It is possible to configure additional features of the JMS resources outlined above to decide on retention periods and other settings. Refer to the <u>Understanding Oracle WebLogic JMS documentation</u> for additional features.

5.7.8 Java Flight Recorder Support

Points to Note:

This feature only applies to Oracle JDK 7u60 and above implementations only.

If Java Flight Recorder is enabled, then these will also be included in Diagnostic Images if <u>Diagnostics</u> is enabled.

The <u>Java Flight Recorder</u> is a component of Java that collected diagnostic and profile data for a running Java Virtual Machine (JVM). Oracle Utilities Application Framework applications now support the enabling of the Java Flight Recorder for tracking online java performance.

To enable the support for Java Flight Recorder in a native installation the following process must be performed on the Oracle WebLogic console:

- Navigate to the Environment → Servers menu item. Click on the product server to enable configuration.
- Navigate to the Server Start tab on the Configuration tab and add the following java options to the Arguments field:

-XX:+UnlockCommercialFeatures -XX:+FlightRecorder

Note: If your site is using the setUserOverrides.sh facility, place these arguments in that script as an alternative.

- Navigate to the General tab on the on the Configuration tab and alter the Diagnostics Volume to the desired number of diagnostics to capture. At a minimum this value should be set to Low.
- Optionally, enable <u>ECID tracking</u> for advanced diagnostics for tracing individual transactions. See <u>ECID Support</u> for details.
- Edit any Diagnostic Modules you are using, or create one if you are not using a module and configure a Dye Injection Monitor as outlined in <u>Configuring the Dye Injection Monitor to Manage</u> <u>Diagnostic Contexts</u>. Filters may be specific to focus the scope of the monitor if desired.

5.7.9 Work Manager Support

Note: This feature only applies to native installation implementations only.

Oracle WebLogic supports WebLogic Server Work Managers which allows implementations to set limits on the server to help optimize performance and prevent server overloading. Oracle Utilities Application Framework applications now allow specification of Work Managers to provide additional throttling capabilities.

To use this feature the following must be performed within the Oracle WebLogic console:

 Create a Work Manager with an appropriate name using the Environment → Work Managers menu item. Target the Work Manager to the product servers using the Targets tab. By default, the Work Manager will be unlimited and have no restrictions.

- The product supports the following constraints:
 - o Minimum Threads Constraint
 - Maximum Threads Constraint
 - Capacity Constraint
- It is also possible to override the action used for Stuck Threads.
- Request Class is currently not supported.
- Save the changes.

Work Managers can be monitored using Oracle WebLogic console or Oracle Enterprise Manager. Refer to the <u>WebLogic Server Work Managers</u> documentation for additional information.

5.7.10 Trust Store Support

Note: For more information about trust stores refer to the <u>JSSE documentation</u> and <u>Keystore</u> <u>Configuration</u> (Document ID: 2014161.1).

Oracle Utilities Application Framework applications now support trust stores as well as key stores for two phase authentications for the online web channel. The format of a trust store is the same as the keystore, but the trust store is used to verify credentials whilst the keystore provides the credentials.

The truststore properties are defaulted in the following user exit file:

 $templates/FW_spl.properties.key store.trust store.include$

If you need to customize any of the properties, refer to the Centralized Properties Customization section in the OUAF installation document.

6. Miscellaneous Configuration

Operations and

This section details the miscellaneous operations that can be performed within Oracle Utilities Application Framework applications, as well as the steps and requirements for its available configurations.

6.1 Enabling Email Logging from Log4j2

The following sample configuration will enable email logging of ERROR level log messages in the ORMB application. When an error is encountered in startup and during operations of the product any ERROR message displayed on the console log file will be emailed to an Administrator's email account or email group.

Points to Note: The change outlined below will make manual changes to a configuration file. Execution of <u>initialSetup</u> may overwrite these changes unless <u>template overrides</u> are used. See <u>initialSetup – Maintain Configuration Settings</u> and <u>Implementing Custom Templates</u> for details. Please ensure you make adequate backups to preserve this change.

Refer to https://logging.apache.org/log4j/2.x/manual/appenders.html#SMTPAppender for details of the appender.

The following changes are required to enable this,

- 1. Open the log4j2.properties in the relevant \$SPLEBASE/etc/conf subdirectory:
 - Web Application Server <u>log4j2.properties Product Logging Configuration</u>
 - Business Application Server log4j2.properties Product Logging Configuration
- 2. Add the following lines to the file:

```
### E1 is an EmailAppender
log4j2.appender.E1 = org.apache.log4j2.net.SMTPAppender
log4j2.appender.E1.Threshold = ERROR
log4j2.appender.E1.layout = org.apache.log4j2.PatternLayout
log4j2.appender.E1.layout.ConversionPattern = %d{ISO8601} [%t] %-5p %c %x - %m%n
log4j2.appender.E1.From = <from>
log4j2.appender.E1.SMTPHost = <SMTPHost>
log4j2.appender.E1.Subject = <subject>
log4j2.appender.E1.To = <to>
###
### The following settings are optional
###
log4j2.appender.E1.SMTPUsername = <SMTPUsername>
log4j2.appender.E1.SMTPPassword = <SMTPPassword>
log4j2.appender.E1.CC = <cc>
```

log4j2.appender.E1.BCC = <bcc>

Parameter	Field from example	Usage
From	<from></from>	Email address for emails
То	<to></to>	Email address/group to send emails to
СС	<cc></cc>	Email address/group to send courtesy copy of emails to
BCC	<bcc></bcc>	Email address/group to send "blind" courtesy copy of emails to
SMTPHost	<smtphost></smtphost>	Host Name of SMTP Server
SMTPUsername	<smtpusername></smtpusername>	Logon User for SMTP Server (if supported)
SMTPPassword	<smtppassword></smtppassword>	Password for Logon User for SMTP Server (if supported)
Subject	<subject></subject>	Subject for email message

3. Modify the following lines in the log4j.properties file:

```
## System-wide settings
# set log levels - for more verbose logging change 'info' to 'debug' ###
log4j2.rootCategory=info, A1, F1, E1
```

- 4. Execute the <u>initialSetup Maintain Configuration Settings</u> utility, with the –w option, to reflect the changes in the WAR/EAR file.
- 5. To deploy the application refer to the <u>Web Application Server Deployment Process</u> or <u>Business Application Server Deployment Process</u>.

6.2 Overriding the Default Oracle Database Connection Information

By default the database connection for Oracle databases is of the format:

jdbc:oracle:thin:@<hostname>:<dbport>:<database_sid>

Where:

Command Line Option	Description
<hostname></hostname>	Database hostname
<dbport></dbport>	Database Listener portname
<database_sid></database_sid>	Database Name

The URL format is described at:

https://www.oracle.com/in/database/technologies/faq-jdbc.html

This configuration setting is sufficient for majority of the environments at a site. If your site requires a specialist URL for RAC support, then you must override the default URL.

To override the default URL, specify the following:

- Log on to the server containing the business application server using the administration account for the desired environment (for example, **splsys**).
- Execute the <u>splenviron</u> utility, with the **–e** option, to attach to the desired environment to change. See <u>splenviron Set Environment Variables</u> for details.
- Execute the <u>configureEnv</u> utility and choose to change menu block 4 (Database). See <u>configureEnv</u>
 <u>Set up Environment Settings</u> for details.
- Change the Database Override Connection String to the desired custom JDBC url.
- Press p to save the change to the ENVIRON.INI.
- Execute initialSetup, with the -t option, to reflect the change in the <a href="https://hibrary.com/
- Execute <u>initialSetup</u>, with the -w option, to include the configuration changes in the WAR/EAR files. This option is not required if <u>externalization of configuration</u> is implemented. See <u>initialSetup</u> <u>Maintain Configuration Settings</u> and Using Configuration Files Outside the WAR/EAR File for details.
- For selected platforms redeployment of the WAR/EAR files is required in accordance with the <u>Business Application Server Deployment</u> process.

The following example uses the Oracle JDBC thin client (for Oracle Real Application Clustering):

```
jdbc:oracle:thin:@(DESCRIPTION =(ADDRESS = (PROTOCOL = TCP)(HOST = machine-name)(PORT = 1251)) (ADDRESS = (PROTOCOL = TCP)(HOST = machine-name)(PORT = 1251) (LOAD_BALANCE = yes) (FAILOVER=YES) (CONNECT_DATA = (SERVER = DEDICATED) (SERVICE_NAME = SID.WORLD)))
```

Refer to the $\underline{\text{Oracle RAC support}}$ for other examples. Example URL using the Oracle JDBC thick client:

idbc:oracle:oci:@SID.WORLD.

Points to Note:

For thick client to work, the Oracle client library directory must be added to the library search path. Oracle client libraries are installed under ORACLE_HOME/lib and ORACLE_HOME/lib32 directories. Add this directory to the library search path environment variable. The library search path environment for AIX is LIBPATH, and for other platforms it is LD_LIBRARY_PATH.

For Oracle Database 12.1 and above, use the format: jdbc:oracle:thin:@<hostname>:<dbport>:/<database_service> to use Pluggable Databases where <database service> is the PDB name.

6.3 Centralized Properties Customization

Support is now added for a centralized properties customization file using which properties present in various configuration files can be customized. Instead of customizing individual properties files, a single file can be used to specify all the properties that are to be customized (add, modify, or remove).

Once specified in this custom central property file, the properties are automatically migrated to specified properties files. All the configuration properties should be specified in the custom centralized properties file "etc/cm_properties.ini" (this can be created as a customization). If the file exists, the content will be processed for the relevant properties.

Each entry in the centralized properties customization file should be specified in the following format:

<PROPERTIES FILE>:<PROPERTY NAME>=<VALUE>

Parameter	Usage
PROPERTIES_FILE	The property file in which the property needs to be added/updated/removed.
PROPERTY_NAME	The name of the property.
VALUE	The value to be added/updated against the property in the specified property file.

- For each property entry (<PROPERTIES_FILE>:<PROPERTY_NAME>=<VALUE>) specified in the
 centralized properties customization file, the property(PROPERTY_NAME=VALUE) is added in the
 specified properties file(PROPERTIES_FILE), if doesn't exist in the specified property file.
- If the property (PROPERTY_NAME=VALUE) already exists in the specified properties file (PROPERTIES_FILE), then the entry is updated with the specified value (VALUE).
- If user doesn't specify the properties file name in the entry i.e., the entry in the centralized properties customization file is "<PROPERTY_NAME>=<VALUE>", then the <PROPERTY_NAME> in all property files is overridden with <VALUE>, if <PROPERTY_NAME> exists.
- In order to remove an existing property from a specific properties file, the centralized properties file will need to have the entry specified as "<PROPERTIES FILE>:<PROPERTY NAME>=[DELETE]"
- In order to remove an existing property from all the properties file, the centralized properties file
 will need to have the entry specified as "<PROPERTY NAME>=[DELETE]"
- Sample entry in the centralized properties customization file:

hibernate.service.properties.template:hibernate.user=clouduser

This sets the hibernate.user property to clouduser in the hibernate.service.properties file.

Note: This feature is implemented if the <u>initialSetup</u> utility is executed with the minimum of —t option. See <u>initialSetup</u> - Maintain Configuration Settings for details.

6.4 Cache Management

Note: If cache management requires global cache management across various nodes, then refer to the Global Cache Flush Support section for more details.

A great deal of information in the system changes infrequently. In order to avoid accessing the database every time this type of information is required by an end-user, the system maintains a cache of static information on the web application server. In addition to the web application server cache, information is also cached on each client browser.

6.4.1 Server Cache

Note: Maintenance of the cache is performed automatically by the ORMB application. Whilst there are commands to force refreshes of the cache, these are designed for administrator and developer use only. Additional security setups are required to enable individual users to access to the facilities below.

The cache is populated the first time any user accesses a page that contains cached information. For example, consider a control table whose contents appear in a drop-down on various pages. When a user opens one of these pages, the system verifies that the list of records exists in the cache. If so, it uses the values in the cache. If not, it accesses the database to retrieve the records and saves them in the cache. In other words, the records for this control table are put into the cache the first time they are used by any user. The next user who opens one of these pages will have the records for this control table retrieved from the cache (thus obviating the database access).

The following points describe the type of data that is cached on the web server:

- **Field labels**: This portion of the cache contains the labels that prefix fields on the various pages in the system.
- System information: This portion of the cache contains installation and license key information as well as basic information about the various application services (for example, the URL's that are associated with the various pages).
- **Menu items**: This portion of the cache contains the menu items.
- **Drop-down contents**: This portion of the cache contains the contents of the various drop-downs that appear throughout the system.
- XSL documents: This portion of the cache contains each page's static HTML.
- **Portal information:** This portion of the cache contains information about which zones are shown on the various pages.

The contents of the cache are cleared whenever the web application server is restarted or as automatically refreshed as controlled by the **fieldValuesAge** parameter on the web application server <u>web.xml</u> configuration file (see <u>Web Application Server Configuration Files</u> for details). This means that fresh values are retrieved from the database upon first use by end users.

If you change the database after the cache is built and the information you changed is kept in the cache, users may continue to see the old values. If you don't want to restart your web application server, you can either use the relevant operation on the JMX FlushBean Mbean available on the web application server or issue a custom browser URL to issue the appropriate command (see below). See Web Application Server JMX Reference for details.

Note: To use the browser URL for the resetting of the cache the user must be logged on to the application's browser interface and have access to the **F1ADMIN** application service.

Function	JSP	MBean Operation
Refresh all cache	flushAll.jsp	flushAll
Refresh all drop-down data	flushDropdownCache.jsp	flushDropDownCache
Refresh field labels	flushMessageCatalog.jsp	flushMessageCatalog
Refresh Fields and FK information	flushFieldAndFKMetaData.jsp	flushFieldAndFKMetaData
Refresh menu items	flushMenu.jsp	flushMenu
Refresh messages	flushMessaging.jsp	flushMessaging
Refresh navigation keys	flushNavigationInfo.jsp	flushNavigationInfo
Refresh portals and zones	flushPortalMetaInfo.jsp	flushPortalMetaInfo
Refresh screen style sheets	flushUI_XSLs.jsp	flushUIXSLs
Refresh security	flushSystemLoginInfo.jsp	flushSystemLoginInfo
Refresh specific drop-down data	flushDropDownField.jsp	flushDropDownField

Points to Note:

It is recommended that the "Refresh all cache" is used for non-production and production systems. The other commands are designed for primarily for development use only. Refer to the *Oracle Utilities SDK* documentation for more information about the options available with the commands.

When using these commands, the cache will be reloaded over time with fresh data. As the data is loaded there is a negligible delay in each transaction that reloads data into the cache for the first time. Therefore, it is recommended not to execute this command frequently.

6.4.2 Client Cache

In addition to the server cache, information is cached on each user browser. After clearing the cache that is maintained on the web application server, it is recommended to also clear the cache that is maintained on the client browser (if possible). To do this, follow the following steps:

Browser	Steps
Mozilla Firefox	Select Tools from your browser menu bar.
	Click Options on the Tools menu.
	 Select the Advanced tab from the Options dialog.
	 Select the Network tab from the Advanced dialog.
	Click on the Clear Now button.
	 Enter the standard product URL to re-invoke the application.

Browser	Steps
Google Chrome/Microsoft Edge	 Click the Customize and control Google Chrome option appearing in the top-most right area of the browser. A list appears.
	 Click the Settings options from the Customize and control Google Chrome menu.
	The Settings page appears.
	 From the left navigation panel, click the Privacy and Security option.
	The Privacy page appears.
	 Navigate to the Privacy and security section and click the Clear browsing data option.
	The Clear browsing data window appears.
	Ensure that the Basic tab is selected.
	 Click all the checkboxes in the Basic tab and click the Clear data button.
	The browser's cache is cleared.

Note: Each user's cache is automatically refreshed as controlled by the maxAge and maxAgel parameters in the web application server web.xml configuration file (see Web Application Server Configuration Files for details). We recommend that you set this parameter to 1 second on development/test environments and 28800 seconds (8 hours) on production environments.

6.4.3 Oracle WebLogic: Expanded or Archive Format

By default, Oracle Utilities Application Framework applications are built into a set of WAR/EAR files and deployed in this format on Oracle WebLogic to operate. For Oracle WebLogic it is possible to use expanded mode rather than the WAR/EAR format. This mode allows the Oracle WebLogic instance directories access to the directories and files used by the JEE components of the product without the need for WAR/EAR files. This has several key advantages:

- Changes to the individual files in the product (such as JSP's or graphics) do not require a rebuild of the WAR/EAR file.
- Outage time to deploy and execute the WAR/EAR file is reduced as Oracle WebLogic reads the files
 directly. In the deployment process, Oracle WebLogic loads the WAR/EAR file and uncompressed
 it to a staging or temporary location for actual execution. This is greatly reduced under expanded
 mode as the files are already uncompressed.
- Application of patches and service packs is faster as the patch installer does not need to rebuild the WAR/EAR files after applying patches.

This expanded mode is suggested for non-production and demonstration environments and is not recommended for production (the default is Archive [non-expanded] mode) as the during the WAR/EAR process additional integrity checks are performed and security control of individual application files adds higher security requirements to production.

applications

ohelp

rest

root

businessapp

The figure below illustrates the expanded mode main directories:

Figure 35: Expanded Format

- Under the root directory are the product specific subdirectories for each subsystem or part of the online component of the ORMB application.
- Under the **businessapp** directory are the business object specific files for each subsystem or part of the online component of the ORMB application.
- The rest directory holds the web service definitions.
- The mobile, XAIApp and help directories are provided for backward compatibility purposes only as those capabilities have been deprecated.

6.5 Implementing Custom Templates

As described in the <u>Web Application Server Configuration Process</u> and <u>Business Application Server Configuration Process</u> the configuration files used in the ORMB application are built from templates. These templates are typically located in the **\$SPLEBASE/templates** subdirectory of each environment.

Note: The file **FW_template_structure.xml** in the **structures** subdirectory lists all the templates and their destination paths. This file should not be altered unless instructed by Oracle Support.

By default, the product uses the base produce provided templates to build the configuration files. These configuration files are usually adequate for most needs in non-production but usually require some customization for production or site-specific standards not covered by the base templates. In the past the site had two options:

 Make custom changes to the configuration file directly – This can be performed against the \$SPLEBASE/etc/conf copies of the configuration files. The issue here is that if the configuration files are reset back to the templates intentionally or unintentionally, using the <u>initialSetup</u> utility, custom manual changes may be lost if not reapplied manually. See <u>initialSetup – Maintain</u> <u>Configuration Settings</u> for details. Make custom changes to base configuration templates – In extreme conditions it was possible to
make manual changes to the base product templates to reflect your site standards and
customizations. The issue is that new releases of the templates for new features would overwrite
any customizations if not reapplied manually.

To address this, it is now possible to override base product templates with a copy of the template (a custom template). This can be achieved by copying the desired base template in the templates directory to the same name prefixed with "cm." The <u>initialSetup</u> utility will use the custom template instead of the base template.

The process to implement this is as follows:

- Identify the template that is used by the desired configuration file. Use the information in the <u>Web Application Server Configuration Process</u> and the <u>Business Application Server Configuration Process</u> sections of this document to help identify the templates used for each configuration file.
- Copy the desired template in the **\$SPLEBASE/templates** subdirectory to the same name but prefixed with a "cm." This will be the override custom template. To disable the custom template at any time either rename the template to another name or remove it from the subdirectory.
- Make the necessary adjustments to the custom template in accordance with your site standards.
 Please follow any conventions used in the template including use of <u>Environment Variables</u> or configuration settings from <u>ENVIRON.INI</u>.
- Use initialSetup in accordance with the <u>Web Application Server Configuration Process</u> and the <u>Business Application Server Configuration Process</u> sections of this document to use the template to generate the new configuration files and incorporate the changes in the product.

Note: If custom templates are implemented, it is the sites responsibility to maintain the custom templates to reflect any changes in the base templates for new, changed or removed functionality.

6.5.1 Additional Templates

The templates mentioned previously in this document are the main configuration file-based templates. There are additional configuration files that are built and used for various purposes. Most of these configuration files are used internally for management of the infrastructure and generation of utilities.

Note: The file **FW_template_structure.xml** in the **structures** subdirectory lists all the templates and their destination paths. This file should not be altered unless instructed by Oracle Support.

There are several areas the templates cover:

- Configuration Files for Oracle WebLogic Oracle WebLogic has specific requirements for configuration settings and files. Refer to the <u>Oracle WebLogic Configuration Support</u> for more specific details.
- Configuration Files for other software Third party software has specific requirements for configuration files.
- **Utilities for deployment** Additional configuration files are built to use in the deployment process to define the ORMB application applications to the relevant runtime software.
- Internal ANT build configuration files Configuration and build files are built to support the configuration build process.

Note: The latter two categories of templates and configurations (utilities and ANT build files) should not be altered unless instructed by Oracle Support.

The table below lists the templates in the template directory not covered by other sections of this document applicable to the online, service, and IWS components:

Templates	Configuration Files	Usage
application.xml.template	application_web.xml	JEE global application configuration file which contains common settings for the web application server.
application_service.xml.templ ate	application_service.xml	JEE global application configuration file which contains common settings for the business application server.
billdirfile.ini.template	billdirfile.ini	Bill Print extract configuration file
boot.properties.template	boot.properties	Oracle WebLogic boot credentials file used for starting server
coherence-cache- config.xml.template	coherence-cache- config.xml	Batch Coherence cache settings
doc1dirfile.ini.template	doc1dirfile.ini	Bill Print extract configuration file
eOBatch.properties.template	eOBatch.properties	Global batch properties
earServiceBuild.xml.template	earServiceBuild.xml	ANT Build file for EAR file for business application server
earWebBuild.xml.template	earWebBuild.xml	ANT Build file for EAR file for web application server
ejb-jar.xml.template	ejb-jar.xml	Generic business application server descriptor for EJB's
Fault.xsd.iws.template	Fault.xsd	Web Services Fault Schema
iws-build- common.xml.iws.template	iws-build.xml	Common settings for IWS Build
iws-build- WLS.xml.iws.template	iws-build.xml	IWS build Settings for Oracle WebLogic
iwsdeploy- log4j2.properties.iws.template	log4j2.properties	Log properties for IWS build process
jarservice.xml.template	jarservice.xml	ANT Build file for jar files
java.login.config.template	java.login.config	JAAS Login file
log4j2.properties.iws.template	log4j2.properties	Log configuration for IWS
log4j2.properties.service.templ ate	log4j2.properties	Log configuration for BAS
log4j2.properties.standalone.t emplate	log4j2.properties	Log configuration for batch

Templates	Configuration Files	Usage
log4j2.properties.template	log4j2.properties	Log configuration for online.
ouaf.jmx.access.file.template	ouaf.jmx.access.file	Default access file for JMX
ouaf.jmx.password.file.templa te	ouaf.jmx.password.file	Default security file for <u>JMX</u>
OUAF-Target.xml.template	OUAF-Target.xml	Oracle Identity Manager interface configuration File. Refer <i>Document ID:</i> 970785.1 on My Oracle Support for details of this integration.
tangasol-coherence- override.xml.template	tangasol-coherence- override.xml	Batch Coherence Overrides
warbuild.xml.template	warbuild.xml	ANT WAR Build file
warupdate.xml.template	warupdate.xml	ANT WAR file for updates
weblogic.policy.template	weblogic.policy	Java Security file used by Oracle WebLogic to protect the product files
weblogic-ejb- jar.xml.template	weblogic-ejb-jar.xml	Deployment descriptor for business application server for Oracle WebLogic

Note: Templates that exist in the **templates** directory but are not mentioned in this document are included in one or more templates above depending on the configuration requirements.

6.6 Sending Emails at the Conclusion of Batch Processes

It is possible to send a notification email when a batch process has ended. This notification happens after the batch process has ended and all application-related commits or rollbacks have taken place. It does not impact the batch process itself in the event of errors happening during the notification process. The default email is a simple text email that contains the batch control, date and time of the submission, run number, submission parameters, batch process summary indicating records processed and in-error, as well as the thread details, including logged messages (up to 100).

The email address can be an individual person or a valid mail group (the latter requires additional configuration in your email system).

To use email notification the email server must be configure using one of the following options:

- The mail server can be defined through the default Message Sender (Class RTEMAILSNDR) with the appropriate SMTP settings on the Context tab.
- Alternatively, the properties can be supplied in the form of JVM properties as follows:

Host whose mail services will be used# (Default value: localhost)

mail.host=<your mail server>

- # Return address to appear on emails
- # (Default value: username@host)
- mail.from=<name@host>
- # Other possible items include:
- # mail.user=
- # mail.store.protocol=
- # mail.transport.protocol=
- # mail.smtp.host=
- # mail.smtp.user=
- # mail.debug=

Name	Туре	Description
mail.smtp.class	String	Specifies the fully qualified class name of the provider for the specified protocol. Used in cases where more than one provider for a given protocol exists; this property can be used to specify which provider to use by default. The provider must still be listed in a configuration file.
mail.smtp.host	String	The host name of the mail server for the specified protocol. Overrides the mail.host property.
mail.smtp.port	int	The port number of the mail server for the specified protocol. If not specified, the protocol's default port number is used.
mail.smtp.user	String	The username to use when connecting to mail servers using the specified protocol. Overrides the mail.user property.
mail.store.protocol	String	Specifies the default message access protocol. The Session method getStore() returns a Store object that implements this protocol. By default, the first Store provider in the configuration files is returned.
mail.transport.protocol	String	Specifies the default message access protocol. The Session method getTransport() returns a Transport object that implements this protocol. By default, the first Transport provider in the configuration files is returned.
mail.user	String	The default user name to use when connecting to the mail server. Used if the mail.protocol.user property isn't set.

These properties can be added to the **threadpoolworker.properties** file for the standalone batch **threadpoolworker**, or the **spl.properties** file for an online application server that hosts a batch worker.

6.7 Oracle WebLogic Configuration Support

Oracle Utilities Application Framework applications have native support for Oracle WebLogic. Normally, the product is installed, and the Oracle WebLogic components are embedded in the directories controlled by the web application server's software during the deployment process. The deployment process usually transfers the WAR/EAR files to the Oracle WebLogic directories.

For Oracle WebLogic, the Oracle WebLogic software can be pointed to directories as in the product installation. This avoids Oracle WebLogic having additional copies of its configuration and WAR/EAR files under its own directory structure.

In this case the following configuration aspects of Oracle WebLogic apply:

- The **\$\$PLEBASE**/splapp subdirectory is referenced directly in the configuration files.
- In non-expanded mode (see <u>Oracle WebLogic: Expanded or Archive Format</u> for details), the WAR/EAR files are directly referenced from the <u>config.xml</u> file.
- In expanded mode (see <u>Oracle WebLogic: Expanded or Archive Format</u> for details), the application files are directly reference in the <u>splapp</u> subdirectories from the <u>config.xml</u> file.
- The config.xml file is located under splapp/config rather than using the Oracle WebLogic location. Any changes made from the Oracle WebLogic console are stored in this file.
- The utilities to start and stop the Oracle WebLogic instance are located under the splapp subdirectory.
- The security configuration files for the Oracle WebLogic instance are located under the splapp subdirectory. The security repository configured is configured in the location supplied with the Oracle WebLogic instance.

Thus, facility allows one installation of Oracle WebLogic to be used across many environments with each environment being independent.

6.8 Using Configuration Files Outside the WAR/EAR File

Typically, the configuration files specified <u>Web Application Server Configuration Process</u> and <u>Business Application Server Configuration Process</u> are embedded into the WAR/EAR files, in accordance with the JEE specification, ready for deployment for use at runtime. While this is generally acceptable for most sites, it also means that any configuration change requires rebuilding of the WAR/EAR files and redeployment to fully implement the configuration changes. This may add outage time to implement configuration changes.

It is possible to allow the ORMB application to use versions of the certain configuration files outside the WAR/EAR files to minimize outage time to implement changes. In most cases, a restart of the product components is necessary to implement the configuration change.

The table below outlines the configuration files that can be externalized from the WAR/EAR file by product component:

Component	Configuration File	Externalized
Web Application Server (root	web.xml – JEE Deployment Descriptor	No
and Webservices)	spl.properties – Product Behavior Settings	Yes
	weblogic.xml – Oracle WebLogic Extensions	No
	log4j2.properties – Product Logging Configuration	Yes
Business Application Server	web.xml – JEE Deployment Descriptor	No
	spl.properties – Product Behavior Settings	Yes
	hibernate.properties – Database Connectivity Settings	Yes
	log4j2.properties – Product Logging Configuration	Yes

By default, the externalization works on the following principles:

- The SPLEBASE environment variable must be set to the home location of the software prior to
 execution of the web application server or business application server. This must match the value
 configured for the environment in the <u>cistab</u> configuration file on the machine. See <u>cistab Global</u>
 Configuration Files for details.
- The external versions of the configuration files should be in their default locations (as supplied) in the \$SPLEBASE/etc/conf subdirectories.
- Your application uses the external configuration file versions instead of the versions embedded in the WAR/EAR files. If you wish to revert to the embedded versions, then the site can either rename the conf subdirectories to prevent the external configuration files being detected or ensuring the SPLEBASE environment is not set.

Warning! If the **conf** subdirectories are renamed they should be reverted to their original names before ANY single fix, service pack or upgrade is performed to prevent configuration reset to base templates or installation failure.

This facility is useful for several situations:

- If any passwords are changed that are used by the product on a regular basis, reflecting changes in the configuration files directly or using templates is easier using externalized configuration files. The WAR/EAR files do not need to be rebuilt and redeployed and this can save time.
- During the initial phases of production or when traffic volumes fluctuate, it may be necessary to tune specific settings. This allows experimentation of the changes before committing to specific values. It allows greater level of flexibility in configuration change.

Note: It is recommended to ensure that in the long term that both the external versions and embedded versions are kept in sync on a regular basis to prevent configuration issues. This can be done using standard maintenance windows as necessary.

6.9 Oracle RAC Support

Note: Refer to the *Oracle Real Application Clustering (RAC)* documentation for setup instructions and parameter settings for RAC. To take advantage of the RAC installation, RAC, including Oracle Notification Service (ONS) for Fast Connection Failover support, must be installed and configured prior to the configuration of the application.

Your application supports the use of Oracle's Real Application Clustering (RAC) for high availability and performance through database clustering. The ORMB application has additional setting to tell the database pooling aspects of the product to take advantage of the RAC facilities.

Once RAC has been installed and configured on the database there are a number of options that can be used to configure the product to use RAC in all modes of configuration:

- It is possible to set up a custom DB Connection string to take advantage of the RAC as outlined in the <u>Overriding the Default Oracle Database Connection Information</u> section of this document. This is the easiest implementation of RAC but does not take advantage of the full RAC features.
- Configure RAC specific settings in the installation configuration files through the **configureEnv.sh** utility. See configureEnv Set up Environment Settings for details.

The following settings should be set:

Environment Settings	Usage	Comments
ONS_JAR_DIR	Location of ONS Jar file (ons.jar)	This is the location of the Oracle Notification Service Jar files for use in the product.
ONSCONFIG	ONS configuration string with RAC server nodes delimited by "," in the form <host>:<port> where <host> is the RAC host node and <port> is the ONS listener port.</port></host></port></host>	Used for connections

Points to Note:

Native RAC Support does not support XA transactions using Universal Connection Pool (UCP) at the present time. If XA compliance is required, it is suggested that JNDI based pools provided by the web application server be used as documented in Using JNDI Based Data Sources.

At the present time Oracle Single Client Access Name (SCAN) is not supported in the configuration of RAC native support.

Once configured, the spl.runtime.options.isFCFEnabled is set to true and spl.runtime.options.onsserver is set to the value specified in ONSCONFIG.

Support for Implicit Connection Caching has been removed as this feature has been superseded by Universal Connection Pool (UCP).

6.10 Adding a Custom Privacy Policy Screen

In certain sites, your application will display a privacy policy to remind users of privacy rules at a site. The product allows for a custom HTML based page to be added by the site. The privacy page should be named privacy.html and placed in the cm directory. You can access the privacy.html using the following url:

https://<host>:<port>/<server>/cm/privacy.html

Where,

Command Line Option	Description
<host></host>	Host Name of the web application server used by the product
<port></port>	Port Number allocated to the web application server used by the product
<server></server>	Server context allocated to web application server used by the product

Refer to the Oracle Utilities SDK on how to add custom HTML to the product.

Once implemented the privacy statement can be obtained from the above URL or from the following URL:

http://<host>:<port>/<server>/privacy

Where,

Command Line Option	Description
<host></host>	Host Name of the web application server used by the product
<port></port>	Port Number allocated to the web application server used by the product
<server></server>	Server context allocated to web application server used by the product

6.11 User Exit Include Files

Whilst the product supports custom templates it is now possible to only supply fragments of a customization rather than whole configuration templates, known as user exit include files. This allows you to specify additional settings to be included in the templates provided in stream when the product templates are used to generate the configuration files when using the <u>initialSetup</u> command. See <u>initialSetup</u> — <u>Maintain Configuration Settings</u> for details.

When initialSetup is executed, the templates are applied with the following order of preference:

- Base framework templates (no prefix). These templates should not be altered.
- If a product specific template exists (prefixed by the product code) then the product template is
 used instead of the base Framework template for the configuration file. These templates should
 not be altered.

• If a template is prefixed with "cm_" then this is a custom template to be used instead of the product specific and base framework template.

These templates should live in \$SPLEBASE/templates.

Note: When creating custom templates please use the base framework and any related product templates as the basis for the content of the custom template.

Whilst this facility is flexible it means that any updates to the base or product templates MUST be reflected in any custom templates. A new option is to use user exits that are placed strategically in the most common configuration files that need change. When initialSetup is executed the existence of user exit files are checked (when an <code>#ouaf_user_exit</code> directive exists in the template) and the contents included in the generated configuration file.

The figure illustrates the process for a typical configuration change:




Figure 36: Include Files

As with the custom templates user exits have preferences depending on the ownership of the user exit include file. Custom includes will override any product specific includes. There are no base includes as they are already included in the template files. The figure below illustrates the preferences for both templates and includes:




Figure 37: Template Hierarchy

The table below outlines the currently available user exits in the available templates:

Template File	User Exit Include file	Position and Usage	
boot.properties.template	boot.properties.exit.include	Used to change boot properties file from Oracle WebLogic	
ejb-jar.xml.template	ejb-jar.xml.wls.jms_1.include	JMS Mappings for Oracle WebLogic	
hibernate.properties.web .template	hibernate.properties.exit.include	At end of file (common <u>hibernate.properties</u> entries)	
	hibernate.properties.web.exit.inc lude	At end of file (online specific hibernate.properties entries)	
log4j2.properties.templat	log4j2.properties.exit.include	At end of file (common log4j2.properties entries)	
	log4j2.properties.root.exit.includ e	At end of file (specific online log4j2.properties entries)	
log4j2.properties.service.t emplate	log4j2.properties.exit.include	At end of file (common log4j2.properties entries)	
	log4j2.properties.service.exit.incl ude	At end of file (specific service log4j2.properties entries)	
ouaf.jmx.access.file.templ ate	ouaf.jmx.access.file.exit.include	Allows for additional users to be specified for JMX connections	
ouaf.jmx.password.file.te mplate	ouaf.jmx.password.file.exit.includ e	Allows for additional passwords to be specified for JMX users	
spl.properties.service.tem plate	spl.properties.exit.include	At end of file (common spl.properties entries)	
	spl.properties.service.exit.include	At end of file for EJB <u>spl.properties</u> entries.	
	spl.properties.service.timeouts.ex it.include	User exit for service timeouts.	
spl.properties.template	spl.properties.exit.include	At end of file (common spl.properties – Product Behaviour Settings entries).	
	spl.properties.root.exit.include	At end of file for Web Application based spl.properties – Product	
		Behaviour Settings entries.	
	spl.properties.timeou ts.root.exit.include	User exit for global timeouts	

Template File	User Exit Include file	Position and Usage
	FW_spl.properties.key store.truststore.incl ude	User exit for keystore and trust store settings.
spl.properties.mobile .template	spl.properties.exit.i nclude	At end of file (common spl.properties – Product Behaviour Settings entries).
	spl.properties.mobile .exit.include	At end of file for mobile Application based spl.properties – Product Behaviour Settings entries.
	spl.properties.timeou ts.mobile.exit.includ e	Future use
submitmitbatch.properti es.template	submitbatch.properties.exit.inclu de	Submitter extensions
threadpoolworker.prope rties.template	threadpoolworker.properties.exi t.include	Threadpool extensions
web.xml.template	spl.properties.images.include	Image processing overrides for web.xml – JEE Deployment Descriptor
	web.xml.servlet_mapping.includ e	Allow custom servlet mappings
	web.xml.servlet.include	Allow custom servlet definitions
	spl.properties.filter_mapping.incl ude	Allow custom filter mappings

To use these user exits create the user exit include file with the prefix "cm_" in the \$SPLEBASE/templates directory. To reflect the user exits in the configuration files you must execute the <u>initialSetup</u> utility. Refer to the <u>Custom JMS Configuration</u> section for an example of this process.

6.11.1 Properties File User Exits

The product behavior is controlled at a technical level by the values in the properties files. Whilst most of the settings are defaulted to their correct settings in the file, additional parameters may be added to the properties files to add new behavior. User exits are used to set these additional parameters in the properties files.

From the table above there are more than one user exit available in each properties file template to use. This is designed to maximize the reusability of configuration settings. There are a number of specialized user exits that you may use:

• Common Settings – The configuration files used by each channel of execution (online, web services and batch) has a common user exit. This user exit is used to house all the setting you want to implement regardless of the channel used. For example, the common setting user exits are:

Configuration File	User Exits for Common Settings
hibernate.properties	hibernate.properties.exit.include
log4j2.properties	log4j2.properties.exit.include
spl.properties	spl.properties.exit.include

• **Channel Specific Settings** – To implement custom settings per channel there is a separate user exit to hold those parameters for those channels. The specific user exits are:

Channel	Configuration File	User Exits for Common Settings
Web App Server	hibernate.properties	hibernate.properties.web.exit.include
	log4j2.properties	log4j2.properties.root.exit.include
	spl.properties	spl.properties.root.exit.include
Business App	log4j2.properties	log4j2.properties.service.exit.include
Server	spl.properties	spl.properties.service.exit.include spl.properties.service.timeouts.exit.include
Inbound Web	log4j2.properties	No User Exit available
Services	spl.properties	No User Exit available
Batch Server	hibernate.properties	hibernate.properties.batch.exit.include
	log4j2.properties	log4j2.properties.standalone.exit.include
	spl.properties	spl.properties.standalone.exit.include spl.properties.timeouts.standalone.exit.includ e

6.12 Custom JMS Configuration

The product includes a realtime Java Message Services (JMS) connector to provide application to application integration. To use this facility, the physical JMS definitions need to be defined as part of the configuration to be included in the configuration of Oracle WebLogic.


Note: It is possible to define the physical JMS configuration using the console provided with Oracle WebLogic, but this may be overwritten during upgrades.

These will match the JMS configuration within the product itself. Refer to the installation documentation provided with the product to understand the required JMS integration.

To reflect the JMS settings a number of custom <u>User Exist Include Files</u> have been provided to implement the JMS changes in the <u>config.xml</u> and <u>ejb-jar.xml</u> configuration files required by Oracle WebLogic.

There are two sets of files that are provided for the JMS integration as examples:

- A set of user exit include files in the scripts/cm_examples/FW/templates directory for the various files necessary to define the physical JMS configuration settings.
- A set of sample XML files that define the attributes of sample JMS settings that are referred to by the custom template user exit include files. These are the files that need to be maintained by the site according to product or local standards.



The figure below illustrates the location of the sample JMS files:

Figure 38: Custom JMS Configuration

To implement the JMS configuration files at your site:

- Log on to the web application server or the business application server machine using the product administration account.
- Execute the splenviron.sh command to orientate to the desired environment you wish to apply the JMS configuration to.
- Create a JMS configuration repository directory under /splapp/config/jms using the following command:

```
mkdir -p $SPLEBASE/splapp/config/jms
```

- Copy the sample XML configuration files to the directory created using the following commands:
 cp \$SPLEBASE/scripts/cm_examples/FW/splapp/config/jms/*
 \$SPLEBASE/splapp/config/jms/
- Copy the user exit include files to the template directory so that the user exits are implemented whenever initialSetup is executed.

```
cp $SPLEBASE/scripts/cm_examples/FW/templates/* $SPLEBASE/templates/
```

Note: To reverse out the change at any time the template files that are copied (prefixed by cm) can be removed from the templates subdirectory under **\$SPLEBASE**.

 Modify the sample XML files in the config/jms directory to suit your product requirements or your site requirements.

At configuration time the settings provided these files are included in the target configuration files as indicated by the user exit include files.

6.13 Online Transaction Timeouts

By default, the product does not impose any transaction time limits on online and web services transactions. If this is not appropriate for your site, then transaction time limits can be implemented globally as well as on individual objects using configuration settings defining the desired transaction time limits.

Specific <u>User Exist Include Files</u> should be used to maintain these settings. To implement these, create or modify the user exit files indicated in the table below in <u>\$SPLEBASE/templates</u>.

To impose global limits the following settings must be added to your user exit files:

Tier/Configuration File	Configuration Settings
Web Application Server (cm_spl.properties.timeouts.root. exit.include user exit file)	Set the ouaf.timeout.query.default parameter to the desired timeout (in seconds) to set a global default on query zones.
Business Application Server (cm_spl.properties.service.timeouts.exit.i nclude user exit file)	 Set the ouaf.timeout.business_service.default parameter to the desired timeout (in seconds) to set a global default on business service invocations.
	 Set the <u>ouaf.timeout.business_object.default</u> parameter to the desired timeout (in seconds) to set a global default on business object invocations.
	 Set the ouaf.timeout.script.default parameter to the desired timeout (in seconds) to set a global default on service script invocations.
	 Set the ouaf.timeout.service.default parameter to the desired timeout (in seconds) to set a global default on application service invocations.

To impose timeout values on individual object/service/scripts then an entry in the business application server cm_spl.properties.service.timeouts.exit.include user exit file must exist for each individual object/service/script to specify the timeout:

Object	Comments
Business Objects	Default:
	<u>ouaf.timeout.business object.default – Set Default</u> <u>Business Object Timeout</u>
	Specific:
	<u>ouaf.timeout.business object. bocode> – Set Specific Business Object Timeout</u>

Object	Comments
Business Services	Default:
	<u>ouaf.timeout.business service.default - Set Default</u> <u>Business Service Timeout</u>
	Specific:
	<u>ouaf.timeout.business service. Business Service Timeout</u>
Query Zones	Default:
	ouaf.timeout.query.default - Set Default Query Timeout
	Specific:
	ouaf.timeout.query. <zonecode> - Set Specific Query</zonecode>
	Timeout
Scripts	Default:
	ouaf.timeout.script.default - Set Default Script Timeout
	Specific:
	<u>ouaf.timeout.script.<scriptname> - Set Specific Script</scriptname></u> <u>Timeout</u>
Application Services	Default:
	ouaf.timeout.service.default - Set Default Service
	<u>Timeout</u>
	Specific:
	<u>ouaf.timeout.service.<service> - Set Specific Service</service></u> <u>Timeout</u>

For example:

ouaf.timeout.service.CILTUSEP=600

Note: Timeout values are not precise as they do not include additional time needed to process any rollback or networking activity necessary after a timeout has occurred.

6.14 Setting the Date for Testing Purposes

One of the common techniques used in testing is to set the date to a fixed point in time to simulate data aging in the product. By default, the date (and time) used in the system is obtained from the database server with the time zone used on the user record to offset (if used by the product). It is possible to override the system date used at a global level or at an individual user level for testing purposes.

Note: This facility is not recommended for use in production environments.

To use this facility the following must be configured:

• Set the spl.runtime.options.allowSystemDateOverride to true in the spl.properties file for the online (Web or Business Application Server) and/or Batch (standalone).

To set the feature at the global level for an environment, navigate to the Administration menu →
 General → Feature Configuration → Add menu option and add a General System Configuration
 Feature Type with the System Override Date option in YYYY-MM-DD format. For example:




Figure 39: Feature Configuration

• If individual test users wish to use different dates, they can set the feature at the user level. This feature does not require the global override setting to be used but if the global override is also used, then this user specific setting is used. To set the date override at the user level, add the Overridden system date Characteristic Type to the individual user record (through Administration menu → Security → User Search menu option) with the Characteristic Value set to the desired date in ▼YYYY-MM-DD format. For example:




Figure 40: System Override for Individual Users

When the facility is active the following applies:

- The facility will only be active if the spl.runtime.options.allowSystemDateOverride parameter is set to true in the relevant spl.properties file.
- If the system override through feature configuration is set, then all users using that channel will use that date for any transactions. If the feature configuration is not set, then the default current date in accordance with the database server is used.
- If users have system date overrides as characteristics, then that user for that channel will use that date regardless if the system override is set or not.

6.15 Secure Transactions

Note: Refer to the *Oracle Revenue Management and Billing Security Guide* for an indepth discussion on implementing SSL.

The product supports HTTP and HTTPS protocols for transmission of data from the browser client and within the architecture. Customers must choose either HTTP (unsecured) or HTTPS (secured) for protocol. Use of both protocols simultaneously is not supported. The default protocol is HTTP.

If you wish to implement HTTPS protocol, then the following process must be used:

- The value for <u>WEB_WLSSLPORT Oracle WebLogic SSL HTTP Port</u> must be specified for the SSL port to use. When this is specified then HTTP is disabled automatically.
- The product ships with the demonstration certificate shipped with the web application server software. It is not recommended to use this certificate for your site. It is highly recommended that you obtain a certificate for your site from a trusted source and install the certificate in accordance with the web application server documentation.
- For all traffic directly to the product please use the https protocol on the URL's used for direct interaction (through the browser or web services interfaces).

Points to Note: For Oracle WebLogic customers, refer to the <u>Configuring Identity and Trust</u> section of the *Oracle WebLogic Installation Guide*.

For both protocols, the PUT, DELETE, TRACE and OPTIONS methods not permitted in the security constraints for the product by default.

6.16 Native Oracle WebLogic Support

Note: The product also now supports the Oracle Fusion Middleware console as an alternative to the Oracle WebLogic console. This manual covers the Oracle WebLogic console only. Customers using the Fusion Middleware console should use the corresponding feature in that console.

One of the features of the product is the ability to use the Oracle WebLogic features in either embedded or native mode. In non-production it is recommended to use embedded mode unless otherwise required. Customers using Oracle ExaLogic for non-production should use native mode to fully support Oracle ExaLogic's architecture.

Whilst all the details of installing the product in native mode is covered in the *Oracle Revenue Management and Billing Installation Guide* a summary of what is required is shown below:

A copy of the Oracle WebLogic must be installed on the machine. This copy of Oracle WebLogic
must not be shared across multiple environments. Using native mode restricts a single copy of the
product to an individual installation of Oracle WebLogic. Customers requiring multiple
environments on a single installation should install multiple Oracle WebLogic installation and use
Oracle Enterprise Manager to manage the multiple instances.

Note: The product now includes a set of base <u>domain templates</u> that can be used with the installation of the product to avoid manual installation issues. <u>Domain Template Builder</u> can also be used to build custom domain templates.

- When using native mode, the product installation should not be placed under the user's home directory or under the Oracle WebLogic home location. It should be installed in a separate location and using the deployment utilities deployed into the Oracle WebLogic domain location.
- Oracle WebLogic must be set up and configured with the following before deployment is to be performed:

Configuration Setting	Comments
Domain should be created	The Oracle WebLogic domain to install the product upon should be created with the Administration Server active on that environment.
Servers should be created	Using the Oracle WebLogic console, the Servers to house the product should be created.
Create XML Registry	Using the Oracle WebLogic console an XML Registry to define the default parser should be created. On AIX this is done at the Oracle WebLogic command line level. Refer to the <i>Oracle Revenue Management and Billing Installation Guide</i> for more details.
Set Java parameters in console	Set the Domain level java settings for memory etc as per the <i>Oracle Revenue Management and Billing Installation Guide</i> .
Define Security	Define the Security Role, Security Realm, and other Security definitions for the product as per the <i>Oracle Revenue Management</i> and <i>Billing Installation Guide</i> .
Create SYSUSER	Create the initial User for the product (SYSUSER) and attach the security role created earlier.
Set SPLEBASE variable	Prior to deployment and execution ensure the SPLEBASE variable is set to point to the location of the product as per the <i>Oracle Revenue Management and Billing Installation Guide</i> .

- To start and stop the online component of the product, in native mode, it is recommended to use
 the facilities provided by Oracle WebLogic. This can be either using the Oracle WebLogic console,
 Oracle WebLogic utilities or through Oracle Enterprise Manager.
- To monitor the online component of the product, use the facilities provided in the Oracle WebLogic console, Oracle WebLogic utilities, or through Oracle Enterprise Manager. Additional monitoring capabilities are available using the Oracle Application Management Pack for Oracle Utilities.
- When making changes to the product anytime the EAR files are changed and therefore, they must be redeployed using the Oracle WebLogic console.

6.16.1 Manual Re-Deployment Process

Whenever the installation EAR/WAR files are updated, they must be redeployed to the JEE web application server to implement the change using one of the following techniques:

 Using the Oracle WebLogic console, use the Update transaction on the selected Deployments. The wizard will remember the last settings, which need to be confirmed, prior to deployment. For example:




Figure 41: Update Oracle WebLogic Deployment

 Use the WLST command line using the <u>redeploy</u> command in the Deployment API. Refer to the WLST Reference for more information.

The following situations require a redeployment event:

- Any execution of <u>initialSetup</u> or <u>initialSetup</u> -w which requires SPLService (or the value of <u>SPLSERVICEAPP</u> Name of <u>Business Application Server Application</u>) and <u>SPLWeb</u> (or the value of <u>SPLWEBAPP</u> Name of <u>Web Application Server Application</u>) to be redeployed. See <u>initialSetup</u> Maintain Configuration Settings for details.
- Any execution of <u>iwsdeploy Inbound Web Services Deployment</u> or online deployment of Inbound Webservices. This requires Webservices (or the value of <u>IWSWAR - Name of Inbound Web Services</u> <u>WAR</u>) deployment.

6.17 Oracle WebLogic Console Operations

Note: Parts of this section do not apply to implementations using the embedded mode. Refer to individual sections for guidance.

When using the native mode of Oracle WebLogic to manage the product, the Oracle WebLogic administration console can be used to perform common operations. This section outlines the common operations that can be used from the console. Refer to the Administration documentation supplied with Oracle WebLogic for further advice.

6.17.1 Starting and Stopping from Console

Note: This facility should only be used for customers using native mode. Customers using embedded mode should use the spl utility.

As the product is using the native mode and native utilities provided by Oracle WebLogic it is possible to manage the product start and stop from the console. To perform this function, the user must do the following:

• Log in to the console designated to administrate the environment using an appropriate administration account.

Note: The default installation account is **system**.

- Select the **Deployments** section of the **Domain Structure**. This will list the deployments to the domain.
- Select the appropriate deployments to start or stop.
- Use the Start or Stop function to perform the start or stop operation, respectively.

For example:




Figure 42: Default Oracle WebLogic Deployments

While it is possible to start or stop individually components it is recommended that all components be started at once to avoid availability issues. If individual components are started or stopped use the following guidelines to minimize issues:

 Be aware of the <u>architecture</u> when stopping components. When starting the product, components lower in the architecture must be started first. When stopping the product, components higher in the architecture should be stopped first. Use the table below as a guide:

Deployment	Role
root	Web Application Server

Deployment	Role
SPLService	Business Application Server
Webservices	Application Integration
javadocs	Data Dictionary

• Stopping non-essential runtime components such as javadocs may result in HTTP 404 error when users select these functions unless they are sourced from other servers.

6.17.2 Monitoring Web Applications Using the Console

Note: This facility is available regardless of mode (i.e., embedded or native) used on the environment.

The Oracle WebLogic administration console can be used to monitor the state and performance of the individual components of the product. This can be achieved using the Monitoring tab of the Deployments option of the Domain Structure section of the Oracle WebLogic administration console.

This allows the following to be monitored:

- **Web Applications** Statistics relating to the web applications deployed to the server. The Context Root and Source Information outlines the individual component monitored.
- JMS If you are using the Message Driven Bean functionality within the product to integrate to
 the JMS resources in the Oracle WebLogic server then statistics related to this function can be
 monitored.
- **EJBs** The Business Application Server and Message Driven Bean functionalities are expressed as Enterprise Java Beans (EJB) and can be monitored from the console. The EJB **SPLServiceBean** is the business application server.
- **Web Services/Web Service Clients** When using the native web service capability, the statistics applicable to individual web services can be monitored.
- **JDBC** If JDBC data sources are manually configured then statistics relating to these connections can be monitored.
- **Workload** By default, Oracle WebLogic allocates simple workload managers for each deployment. These workload managers and any custom constraints can be monitored.

Refer to the *Oracle WebLogic* documentation for a detailed description of each of the statistics and their relevance.

6.18 Specifying Custom Log File Names

By default the <u>submitjob</u> and <u>threadpoolworker</u> utilities will create logs in a specific location. For example:

User Exit	Platform	Default Location and Name	
submitjob.sh	UNIX	\$SPLOUTPUT/submitjob.{batchCode}.{sysDateTime}.log	
threadpoolworker.sh	UNIX	\$SPLOUTPUT/threadpoolworker.{sysDateTime}.{pid}.log	

Where:

Commands	Description
{batchCode}	Batch Control used for job
{sysDateTime}	System Date and Time in YYYYMMDDHHmmSSSSS format
{pid}	Process ID

If your implementation wishes to implement custom log file names, then this may be achieved using user exits which allow custom setting of the file name pattern. In the utilities an environment variable is set to the name and location of the log file. The user exit may be used to set this environment variable to an alternative. The user exit contains the script code fragment used to set the log file environment file name.

The table below lists the user exit, environment variable name and the platform:

User Exit	Platform	User Exit Name	Env Variable
submitjob.sh	UNIX	submitjob.sh.setvars.include	SBJLOGID
threadpoolworker.sh	UNIX	threadpoolworker.sh.setvars.include	TPWLOGID

Additionally, internal session variables are available for use in the user exits:

Variable	submitjob	threadpoolworker	Comments
RUNOPTS		•	Runtime Options
batchCode	•		Batch Code
sysDateTime	•		Run Date and Time

Points to Note:

Other environment variables in the session can be used and determined in the user exit script code. submitjobs are set for Java runtime.

6.19 Turning Off L2 Cache

Note: This facility should only be used where background processes specifically require it. Turning off the cache in other circumstances will adversely affect performance.

By default, the threadpools use a batch cache to load common configuration data to avoid excessive calls to the database. In some cases, it is desirable to disable the caching for a particular threadpool. To disable the cache on startup of the threadpool use the following command:

threadpoolworker.sh -l2 OFF -p <threadpoolname>

where <threadpoolname> is the name of the threadpool to start with the caching disabled.

Once the threadpool is started then all jobs that require caching off can be executed in this threadpool using the DIST-THD-POOL parameter (for online submission), com.splwg.batch.submitter.distThreadPool Threadpool parameter in the job specific properties file or -p option on the submitjob command. See submitjob.sh - Submitjob (Legacy method of batch submission).

6.20 JDBC Support

Note: This facility is only available for online and web services channels only.

By default, the product uses the Universal Connection Pooling (UCP) to manage database connections. It is also possible to use Oracle WebLogic connection pooling through Data Sources for the online transactions (UCP will continued to be used for batch transactions). To use Data Sources the data sources must be created within Oracle WebLogic and then configuration files altered to utilize the Data Source using the following process:

 Create the Data Source in the Oracle WebLogic console using the Services → Data Sources menu item. Repeat for the connection pool for online and connection pool for web services. Specify the following:

Attribute	Comment	
Name	Allocate a name for monitoring and management purposes	
JNDI Name	Allocate a name to be used by the connection. This is used as datasourcename later. It is recommended that the name be prefixed with jdbc/ to conform to naming standards.	
Row Prefetch Enabled	This should be enabled.	
Row Prefix Size	Specify a value between 2 to 100. Default: 48	
Stream Chunk Size	This is not used by the product	
Database Type	Specify Oracle	
Database Driver	Specify the database driver to use. Do not use the XA versions of the driver for the product. By default, use the Thin driver for Service Connections.	
Supports Global Transactions	Deselect this option as it does not apply.	
One Phase Commit	Ensure this option is selected.	
Database Name	Specify the Oracle SID of the database to connect to. This should correspond to DBNAME – Database Name in the ENVIRON.INI .	
Host Name	Specify the host allocated to Oracle. This should correspond to DBSERVER in the ENVIRON.INI .	
Port	Specify the Oracle Listener Port number of the database to connect to. This should correspond to DBPORT - Database Listener Port in the ENVIRON.INI .	
Database User Name	Specify the product database user. This should correspond to DBUSER — Online Database User in the ENVIRON.INI . If creating a separate connection pool for web services then it is recommended to use XAI_DBUSER - Database User Used for IWS in the ENVIRON.INI to separate traffic in the database.	

Attribute	Comment
Password	Specify the password for the user. This should correspond to DBPASS in the ENVIRON.INI.
	If creating a separate connection pool for web services then it is recommended to use XAI_DBPASS — Password for Database User for IWS in the ENVIRON.INI to separate traffic in the database.
Initial Capacity	This is the initial size of the connection pool
Maximum Capacity	This is the maximum size of the connection pool
Capacity Increment	This is the number of connections that are added to the connection pool when necessary.
Statement Cache Type	This denotes the type of cache to use. Use the LRU setting.
Statement Cache Size	This is the cache size.

• Specify the following values in the <u>ENVIRON.INI</u> using the <u>configureEnv</u> utility, See <u>configureEnv – Set up Environment Settings</u>.

Setting	Recommendation
IWS JDBC DataSource Name	Fully qualified JNDI Name for Web Services Data Source
Web JDBC DataSource Name	Fully qualified JNDI Name for Web Data Source

- Execute the <u>initialSetup</u> utility to reflect the change.
- If using native mode, <u>redeploy</u> the product EAR files. See <u>Manual Re-Deployment Process</u> for details.

6.21 Cancelling Batch Processes Using JMX

While JMX can be used to obtain monitoring information it is possible to cancel threads of batch processes using the operations component of JMX. To cancel a thread the following process must be performed:

- Start the JMX console of your choice and connect to the relevant JMX port configured for the batch.
- Select the thread and batch process to be canceled from the JMX console.
- Select the Cancel operation from the operations component of the console. The console may recognize the operations of the JMX classes and allow the actions to be processed. For example, jconsole will generate the cancelThread button. Issue the action.



Figure 43: CancelThread Example

Note: Depending on the JMX console used, a confirmation dialog may NOT be displayed and cannot be undone once issued. Ensure that the correct thread for the batch process is selected. To cancel a batch process, ALL threads must be canceled.

The batch process will be marked as canceled and stopped. The IP address of the requester is logged in the **Batch Run Tree** for auditing purposes.

7. Operations from Oracle Enterprise Manager

Note: This section of the Oracle Revenue Management and Billing Server Administration Guide provides an overview of using Oracle Enterprise Manager along with the Application Management Pack for Oracle Utilities to administer your application.

This section assumes that Oracle Enterprise Manager and the Application Management Pack for Oracle Utilities are installed prior to using this section. If this is not the case, refer to the installation documentation for these products to complete that prerequisite installation.

7.1 Discovering Oracle Utilities Targets

Prior to using Oracle Enterprise Manager, the Oracle Utilities targets must be discovered and registered with the Oracle Management Repository (OMR) within an Oracle Management Server (OMS) using Oracle Management Agents (OMA).

To discover the Oracle Utilities targets the following process must be followed:

• Install the Oracle Management Server and Oracle Management Repository to the relevant centralized server in accordance with the Oracle Enterprise Manager documentation.

Note: It is not recommended to install the Oracle Management Server or Oracle Management Repository on the same servers housing the products.

- Deploy the Oracle Management Agents to the hosts housing the products.
- Discover and register the hosts and agents to the Oracle Management Repository using any of the methods described in the Oracle Enterprise Manager documentation.
- Start the products using the console or scripts.

Note: Oracle Enterprise Manager will only discover and register targets that are active at the time of discovery.

- Deploy the base Fusion Middleware functionality to the agents on the hosts for the products.
- Discover the Fusion Middleware targets associated with the product. This includes the domain, servers, and application deployments.
- Download the Application Management Pack for Oracle Utilities through <u>Oracle Software Delivery</u>
 <u>Cloud</u> or Oracle Enterprise Manager Self Update.
- Deploy the Application Management Pack for Oracle Utilities to the Oracle Management Server to enable the server content.

Note: This may require a short outage on the Oracle Management Server.

- Deploy the Application Management Pack for Oracle Utilities to the Oracle Management Agents on the product hosts to enable agent content.
- Discover the Oracle Utilities Environment target using the Discovery process as documented in the Oracle Enterprise Manager documentation. All related targets will be automatically discovered.

Note: At discovery time, target names are autogenerated. They can only be renamed with more meaningful names at discovery time.

After discovery of the Oracle Utilities Environment target the following Oracle Utilities targets are discovered, registered, and associated with the Oracle Utilities Environment target:

- Oracle Utilities Web Application Target One or more web application server targets (SPLWeb)
 associated with the Oracle Utilities Environment target. This target is associated with the Fusion
 Middleware web application server base target.
- Oracle Utilities Web Services Target One or more business application server targets (SPLService) associated with the Oracle Utilities Environment target. This target is associated with the Fusion Middleware web application server base target.
- Oracle Utilities Home Target One or more software installations associated with the product associated with the Oracle Utilities Environment target.
- Oracle Utilities Batch Server Target One or more Coherence hosts associated with the Oracle Utilities Environment target.

7.2 Discovering Oracle WebLogic Targets

Oracle Enterprise Manager can discover and manage the products using the Oracle Application Management Pack for Oracle Utilities.

It is possible to manage and monitor the database and Oracle WebLogic from Oracle Enterprise Manager. When using native mode, Oracle Enterprise Manager will autodiscover the Oracle WebLogic instance using its native facilities. To use Oracle Enterprise Manager with environments using the default embedded support of Oracle WebLogic the following can be used to discover and monitor the instance:

- Within Oracle Enterprise Manager Console, navigate to the **Add Targets Manually** menu option under the **Setup** menu.
- Select Add Non-host Targets using Guided Process from the options list.
- Select Oracle Fusion Middleware to denote that Oracle WebLogic will be discovered.
- In the dialog specify the following values:
- Administration Server Host The host name used for WL_HOST in your environment. This host must be registered to Oracle Enterprise Manager as a target so that the agent is redeployed.
- Port The port number assigned to the environment (WL_PORT).
- Username An account authorized to the Oracle WebLogic console. The Oracle Utilities
 Application Framework installer creates an initial user system that can be used if you have not got
 a site-specific value for this user. This User ID is used, by default, for all operations to the target. It
 must be an Administration account not a product account.
- **Password** The password configured for the Username.
- Unique Domain Identifier A unique identifier for the domain to denote within Oracle Enterprise Manager. This is important and should be some value that means something for your administrator to understand. This also allows multiple targets per host to be defined easily. Make sure you do not use any embedded blanks and special characters for the name.
- **Agent** This is the default host and port for the OEM agent on that machine. Just for references and can be altered if the default port is different for OEM at your site.

- Choose to Continue and the above target will be registered for use within Oracle Enterprise Manager.
- Each server in your domain will be registered as an Oracle WebLogic Server and every component of the product will be registered as an Application Deployment. For example:




Figure 44: Oracle WebLogic Targets

7.3 Oracle Utilities Targets

The following targets are available for your application:

Target	Usage
Oracle Utilities System Environment	Environment Target as a collection of other targets
Oracle Utilities Home	Software installation(s) for environment. Used to cloning and patching
Oracle Utilities Web Application	Online Web Applications
Oracle Utilities Web Services Application	Business Application Server Applications
Oracle Utilities Batch Server	Threadpool/Submitter Batch Servers

Refer to the <u>Oracle Application Management Pack for Oracle Utilities Overview</u> (Document ID: 1474435.1) for more information.

7.4 Monitoring Using Oracle Enterprise Manager

The following target types within Oracle Enterprise Manager can be used with your application directly:

Target	Monitoring Capabilities
Oracle Utilities Web Application	Availability for online transaction including Oracle WebLogic basic metrics.
Oracle Utilities Web Services Application	Online performance monitoring (see Business Application Server JMX Reference)
Oracle Utilities Batch Server	Batch performance monitoring (see Batch JMX Reference)

Target	Monitoring Capabilities
Oracle WebLogic Server	Availability, JMS, MDB and URL performance information
Application Deployment	Individual deployment metrics for Online, Business Application Server and Inbound Web Services including availability, performance, and other metrics.
Java Virtual Machine	JVM Diagnostics (if Oracle WebLogic Management Pack EE installed)
Database Instance	Database metrics including performance and availability

Note: It is not recommended to use the Oracle Coherence targets within Oracle Enterprise Manager for monitoring or managing the batch cluster.

8. Oracle Scheduler Integration

Note: The Oracle Scheduler interface is an optional installation for using the Oracle Scheduler in the Oracle Database to schedule and execute product jobs. Customers using alternative methods or tools can ignore this section.

8.1 Introduction

The Oracle Utilities Application Framework application now includes optional interfaces to the Oracle Scheduler, which is part of the Oracle Database. These interfaces allow the management of Oracle Scheduler objects and the execution of product batch processes using the scheduling capabilities of the Oracle Scheduler.

8.2 Background Materials

Before reading this section, it is recommended to familiarize yourself with the Oracle Scheduler by reading the following documentation:

- Oracle Scheduler Concepts Overview of the scheduler including the architecture.
- <u>Scheduling Jobs with Oracle Scheduler</u> Creating, running, and monitoring jobs, chains and prioritization.
- <u>Administrating Oracle Scheduler</u> Configuration, monitoring, import/export schedules, troubleshooting, and so on.
- <u>Using Oracle Scheduler with a CDB</u> Using Oracle Scheduler in and/or with a multi-tenant container database.
- <u>DBMS_SCHEDULER_Reference</u> Reference API for the Oracle Scheduler including all the valid procedures available.

Note: The Oracle Scheduler in Oracle Database 12c and above is recommended to be used for this interface.

8.3 Oracle Scheduler Interface Overview

The product now includes REST services that lets users manage Oracle Scheduler objects using product services. This interface makes it easier to integrate batch schedules with enterprise schedulers.

- These are a set of services (invoked through REST APIs) to create, update, read, delete, and execute
 Oracle Scheduler objects. These services are managed within the product itself. These services
 internally invoke necessary Oracle Scheduler functions to manage and monitor schedules and
 batch executions.
- Following set of OUAF business services can be invoked using REST to manage Oracle scheduler objects: (detailed interface definition is mentioned in the <u>Oracle Scheduler – REST APIs</u> section):
- F1-DBMSProgram Add, read, change, or deletes a DBMS Scheduler Program object based on the action provided.
- F1-DBMSChain Add, read, change, or deletes a DBMS Scheduler Chain object based on the action provided.

- F1-DBMSSchedule Add, read, change, or deletes a DBMS Scheduler Schedule object based on the action provided
- F1-DBMSJob Add, read, change, or delete a DBMS Scheduler Job object based on the action provided
- F1-DBMSList Retrieves a list of names and descriptions of scheduler object based on the type provided and an optional name to filter with
- F1-DBMSSubmitJob Submits a scheduler job for execution.
- F1-DBMSGetJobDetails Retrieves the details of DBMS Scheduler Job based on job name
- F1-GetDBMSJobs Retrieves a list of scheduler jobs based on status. The output is either a list of running jobs or a list of completed jobs based on the status provided.
- F1-DBMSCancellob Uses the service defined above to cancel a DBMS Scheduler Job.
- F1-DBMSRestartThread Uses the service defined above to restart a batch job thread.
- F1-DBMSRestartChain Uses the service defined above to restart DBMS Scheduler Chain.

In addition to the above, the product includes interfaces to allow Oracle Scheduler to schedule and execute product batch processes.

The components of interface are as follows:

- A set of tables to configure and control the interface. These tables are not managed by any object
 within the product itself as they are exclusively reserved for internal use by the Scheduler
 interface. These are installed in the product schema.
- A PL/SQL procedure (<u>Oracle Scheduler Interface (OUAF_BATCH</u>)) that implements an interface to
 Oracle Scheduler to populate the scheduler interface tables, execute jobs, and manage jobs from
 the PL/SQL interface supported by the Oracle Scheduler. This is installed on the product schema.
- The scheduler object may exist on the same database as the product or remotely on a scheduler database. If the remote option is used then the <u>Oracle Scheduler Agent</u> must be installed and enabled on the product database servers. A <u>destination</u> and <u>credentials</u> must also be configured.

Note: The Oracle Scheduler Agent is an option on the database installation or the Oracle Client installation.

- If <u>File Watchers</u> are used on product software hosts, then the <u>Oracle Scheduler Agent</u> must be enabled to access the files on the hosts holding the file.
- No user interface components are supplied with the interface from the product itself. The Oracle Scheduler uses Oracle SQL Developer or Oracle Enterprise Manager to maintain, execute and monitor Oracle Scheduler objects. It is recommended customers and partners use those interfaces to manage your schedule and related objects for Oracle Scheduler.
- For the Oracle Scheduler Interface to operate at least one threadpool.
- The Oracle Scheduler interface must be installed on the product schema, but the schedule can be
 maintained locally or remotely. To support remote invocations, it is highly recommended to set up
 a dedicated database user for the schedule which is independent of the product database users.
 The product installation guide uses the default SCHADM for this role. All schedule information is
 stored in this schema not the product schema.

Note: This manual will use the default value for this schedule administrator **SCHADM**, but the actual implementation may vary.

8.3.1 Oracle Scheduler Configuration

The Oracle Scheduler interface is installed on the product database and optionally on the scheduler database (for enterprise-wide deployments).

After the Oracle Scheduler interface is installed the scheduler interface operates on the following principles:

The Oracle database holding the schedule must have the JOB_QUEUE_PROCESSES set to the
maximum number of total concurrent threads expected to execute at peak times to ensure
maximum thread usage.

Points to Note:

The default is set to 1000 jobs, unless altered.

This includes any DBA tasks and non-product processes that use the Oracle Scheduler at any time.

- The Oracle Scheduler and interface are configured to define the preferences to set the behavior:
 - The Oracle Scheduler preferences are configured with global scheduling defaults including email servers, time zones etc. For more information on the Oracle Scheduler preferences refer to Setting Scheduler Preferences and Order of Preference.
 - The Oracle Scheduler Interface options are set appropriately. For more information refer to Scheduler Interface Options.
- The Oracle Scheduler is configured with the following minimal schedule objects. Additional objects can be configured as outlined in Scheduler and Using Additional objects in Oracle Scheduler.
- **Job** Define one or more jobs per Batch Control using the <u>Submit Job</u> interface. Refer to <u>Defining</u> Jobs for additional interface advice.
- **Chain** Define the dependency chain with all the jobs that need to be executed with that chain. Refer to Defining Chains for additional advice.
- Optionally, populate the parameters of each job as outlined in Specifying Job Parameters.

8.3.2 Oracle Scheduler Execution

Note: The threadpools used by any process must be started before any job can execute.

Refer to the Scheduler Architecture of how the Oracle Scheduler internally operates.

Once the scheduler objects are defined the Oracle Scheduler will initiate the batch jobs using the following technique:

- When a job in the Scheduler is deemed ready to execute, the Oracle Scheduler Interface determines the parameters from the various objects (including from the PL/SQL command line) and creates entries in the batch instance tables.
- The product batch daemon detects a pending process and distributes the job to the threadpools indicated on the job parameters for execution. The Oracle Scheduler does not distribute the jobs to the threadpools that is done through the daemon.

- During execution the monitoring capabilities in Oracle Scheduler, Oracle Enterprise Manager, JMX
 or the Batch Run Tree can be used to monitor the process. Refer to Monitoring Oracle Scheduler
 for more information.
- If the batch process fails, the interface set the job to the FAILED state for the Oracle Scheduler to react accordingly. If the batch process completes successfully the interface will set the job to the SUCCEEDED state for the Oracle Scheduler to react accordingly

The following figure summarizes the flow and processing for the Oracle Scheduler, the Oracle Scheduler Interface and batch architecture:




Figure 45: Oracle Scheduler Interface

8.4 Oracle Scheduler Interface (OUAF_BATCH)

The Oracle Scheduler Interface is a PL/SQL based package **OUAF_BATCH** which contains several procedures to initiate batch processes, cancel running batch processes and manage the parameters for the interface.

8.4.1 Submit_Job - Submit a Job or Thread

The **Submit_lob** procedure submits a batch job and waits for it to complete or fail. It returns COMPLETED or FAILED state to the Oracle Scheduler when used in a Job or Program object.

Column Name	Data Type	Required	Description
batch_code	Text		Valid batch control
user_id	Text	•	Valid product user defined in user object. The email address specified on the user object is used to send any configured notifications. Value can be inherited from configured parameters.

Column Name	Data Type	Required	Description
thread_count	Number		Override for thread count on batch control.
business_date	Date		Process date to be used for batch job. Value can be inherited from configured parameters. Value can be set using the to date function. If no value is provided, the current date will be used. The format of the date must be in a recognizable format. For example, DD-MMM-YYYY is supported. It is recommended to use the to date function to avoid confusion.
max_timeout_mins	Number		Maximum timeout, in minutes, for transactions to avoid <u>ORA-01555</u> <u>Snapshot too old errors</u> . Default is 15.
rerun_number	Number		Used for rerunning specific extracts. Default is: • (zero) for current extract.
thread_pool	Text		Valid Threadpool name to execute this batch job. This corresponds to the DIST-THD-POOL parameter. If not provided at all, the value of DEFAULT is assumed.
min_run_status	Number		Minimum Run Status that will cause this procedure to exit. The default is RUN_STAT_COMPLETED (40). Other values supported: 10 - RUN_STAT_PENDING 20 - RUN_STAT_IN_PROGRESS 30 - RUN_STAT_ERROR 40 - RUN_STAT_COMPLETED

Column Name	Data Type	Required	Description
raise_error	Boolean		If the min_run_status is set a value less than 40, this parameter is set to true, and the job status matches the value of the min_run_status then raise an application error. This allows the chain to support conditional branches or stop chains on conditions. Default is false.
thread_notification s	Boolean		Whether if an error in any thread should trigger a notification event. Default is true. See Notification Options for more information.
single_submitter	Boolean		Whether multiple threads should be submitted as separate jobs. Set this to false to enable separate job submissions for each thread.
soft_parm_map	Array		Associate array of soft parameters. Refer to <u>Specifying Job Parameters</u> for more details.
soft_parm_list	Array		Table array of soft parameters. Refer to Specifying Job Parameters for more details.

Example command lines:

```
begin
   OUAF_BATCH.Submit_Job(batch_code => 'F1-SYNRQ', user_id => 'FRED01',
        thread_count => 4, business_date => '01-JUN-15', max_timeout_mins => 15,
        rerun_number => 0, thread_pool => 'DEFAULT', min_run_status =>
        OUAF_BATCH.RUN_STAT_COMPLETED, raise_error => true, thread_notifications =>
        true, soft_parm_list => OUAF_BATCH.parm_list_t('someParm','someValue'));
end;
begin
   OUAF_BATCH.Submit_Job(batch_code => 'F1-SYNRQ', user_id => 'FRED01');
end;
begin
   OUAF_BATCH.Submit_Job(batch_code => 'F1-SYNRQ', user_id => 'FRED01');
business_date => to_date('2016-01-01','YYYY-MM-DD'), thread_count => 1);
end;
begin
```

```
OUAF_BATCH.Submit_Job(batch_code => 'F1-SYNRQ', user_id => 'FRED01', thread_pool => 'POOL01');
end;
begin

OUAF_BATCH.Submit_Job(batch_code => 'F1-SYNRQ', user_id => 'FRED01', soft_parm_list => OUAF_BATCH.parm_list_t('maintenanceObject','F1-SYNC REQ', 'isRestrictedByBatchCode','true'));
end;
begin

OUAF_BATCH.Submit_Job(batch_code => 'F1-SYNRQ', user_id => 'FRED01', business_date => to_date('2015-06-01','YYYY-MM-DD'));
end;
```

8.4.2 Restart_Thread - Restart a Failed Thread/Job

If a batch job or a thread of a job has failed and needs to be restarted the **OUAF_BATCH** includes an operation to restart the thread.

The **Restart_Thread** procedure uses the same parameters of the **Submit_Job** procedure with an additional parameter:

Column Name	Data Type	Required	Description
thread_number	Number	•	Thread Number to restart. For single threaded jobs, this should be set to 1.

The parameters can match the original execution or be altered to change the behavior of the individual thread.

Note: The **thread_count** should match the original to ensure all data is processed correctly.

The major difference between **Submit_Job** procedure and **Restart_Thread** procedure is that **Restart_Thread** procedure does not wait for the thread to complete. It simply ends after submitting the thread. Therefore, it is not recommended to be used in a schedule in Oracle Scheduler.

Examples of the command are as follows:

begin

```
OUAF_BATCH.Restart_Thread(batch_code => 'F1-SYNRQ', thread_number => 2, user_id => 'FRED01', thread_count => 4, business_date => '01-JUN-15', max_timeout_mins => 15, rerun_number => 0, thread_pool => 'POOL01');
```

end

8.4.3 Cancel Job - Cancel a Running Job

Note: This technique is an alternative to the technique outlined in **Batch JMX Reference**.

The dbms scheduler.stop job procedure is recommended to stop a scheduler job.

A job that is executing can be stopped using the Cancel_Job procedure. The procedure can use one of the following identifiers to cancel the running job.

Column Name	Data Type	Description
batch_code	Text	Valid batch control
job_id	Number	Allocated job identifier from batch daemon (on ci_batch_job table).

For example:

```
Begin
    OUAF_BATCH.Cancel_Job(job_id => '00000000000123', batch_code => 'F1-SYNRQ');
end;
Begin
    OUAF_BATCH.Cancel_Job(job_id => '00000000000123');
end;
Begin
    OUAF_BATCH.Cancel_Job(batch_code => 'F1-SYNRQ');
end;
```

The Cancel_Job procedure asynchronously changes the running Submit_Job status to CANCELED state and terminates. The Submit_Job instance continually monitors the status and will take appropriate action to cancel all the running threads and end with a cancellation error once all the threads have ended. Refer to Cancellation for more details.

8.4.4 Set_Option - Set a Global or Job Option

The **Set_Option** procedure is used to set global or job specific options for the scheduler interface. Any option specified using this procedure is subject to the <u>Order of Preference</u> for parameters.

The **Set_Option** procedure uses the following command format:

```
begin
OUAF_BATCH.Set_Option(scope => '<scope>', name => '<parmname>', value => '<parmvalue>');
end;
```

Command	Description
<scope></scope>	Scope of the parameter. The valid values are GLOBAL for global settings or a valid Batch Control for a specific Batch Control. Settings at the Batch Control level override the GLOBAL scope.
<parmname></parmname>	The parameter name from the list below. This setting can be overridden on the command line.
<parmvalue></parmvalue>	The value of the parameter designated by <pre>parmname> to be used for the scope designated by <scope>.</scope></pre>

The parameters supported by this option are listed below:

Parameter Name	Description
business_date	The default business date is the database's current system date, but this can provide an alternative default. It is typically useful in the case of jobs that run past midnight to make it maintain the same date for all the submissions. The date format is ISO format: YYYY-MM-DD.
user_id	The User ID is required for every submission but to avoid having to specify it on every Submit_Job call, this will define a default either globally or for specific batch codes. The user must be defined as a user object within the product.
poll_seconds	By default, the batch tables are checked every 1 second for updates. This provides for very responsive job handling, but if it is too taxing on the database, the frequency can be modified with this setting. The value must be between 1 and 60.
notify_job_name	Oracle Scheduler job OUAF_NOTIFY is the default thread notification job. That is defined out of the box to send emails for every failed thread. If that behavior is undesired, a custom thread notification, Oracle Scheduler job can be created, and it defined as the default handler with this option. The new notify Oracle Scheduler job must exist.
thread_notifications	Set to false to suppress thread notifications for failed threads. The default is true.
thread_pool	The default threadpool to use. The installation default threadpool is 'DEFAULT'.
discard_queue	Set to true to delete all unused online job queue entries (CI_BATCH_JOB rows) created by OUAF_BATCH. The default is false. OUAF_BATCH uses individual CI_BATCH_JOB rows for the threads so it may become quite voluminous, and the job queue entries are typically not useful once a thread has started executing as the Batch Run Tree entries are used to track the job. This option can be used to clean up the unused entries.

Parameter Name	Description
debug	Set to true to see internally generated DBMS_OUTPUT debug messages. The default is false . Used for development purposes.
single_submitter	Set to true to submit a separate job for each thread of batch job. Default behavior is to submit a single job for multiple threads of batch job.

For example:

Begin

```
OUAF_BATCH.Set_Option(scope => 'GLOBAL', name => 'user_id', value => 'FRED01');
```

end

To remove the option, use the Unset Option (see Unset Option - Reset a Global or Job Option) procedure.

8.4.5 Unset Option - Reset a Global or Job Option

By using the <u>Set_Option</u> feature sets the global or job specific parameters for the scheduler it is possible to also remove the settings using the <u>Unset_Option</u> feature on the parameters covered by the <u>Set_Option</u> feature. The format of the command is:

begin

```
OUAF_BATCH.Unset_Option(scope => '<scope>', name => '<parmname>');
```

end;

Parameter Value	Description
<scope></scope>	Scope of the parameter to reset. The valid values are GLOBAL for global settings or a valid Batch Control for a specific Batch Control.
<parmname></parmname>	The parameter name to reset. Refer to the <u>Set Option</u> (see <u>Set Option - Set a Global or Job Option</u>) procedure for the valid list.

For example:

begin

```
OUAF_BATCH.Unset_Option(scope => 'GLOBAL', name => 'business_date'); end:
```

8.4.6 Raise Thread Error - Raise an Error

Whenever a thread or job fails the Oracle Scheduler Interface informs the product of the failure as well as the scheduler itself. This is handled by the Raise_Thread_Error. This procedure is not directly called by the scheduler itself and is used internally by the interface itself.

8.5 Building a Schedule

Note: This section summarizes the features of the scheduling jobs in Oracle Scheduler using the Oracle Scheduler integration. Refer to the Scheduling Jobs with Oracle Scheduler for additional information.

To use the Oracle Scheduler the scheduler objects must be loaded and the command lines use the provided Oracle Scheduler Interface PL/SQL package.

8.5.1 Recommended Tools

There are several tools that are recommended to be used to define, maintain, and manage the Oracle Scheduler:

- PL/SQL interface There is a PL/SQL based command line interface that can be used to define the
 scheduler objects and control the scheduler through the DBMS_SCHEDULER package from any
 SQL interface tool. For more information about the PL/SQL interface, refer to the
 DBMS_SCHEDULER Reference. This is useful for direct access environments. It is also used by the
 other tools, through generated statements, to manage the Oracle Scheduler.
- **Oracle SQL Developer** Oracle SQL Developer includes an interface to manage scheduler objects including wizards to define key objects. For example:




Figure 46: Example Oracle SQL Developer Oracle Scheduler Interface

• **Oracle Enterprise Manager** - The database targets associated with the Oracle Scheduler allow for the definition, management, and monitoring scheduler objects. For example:




Figure 47: Example Oracle Enterprise Manager Oracle Scheduler Interface

It is possible to use any of the interfaces above to manage your schedule objects. Refer to the help pages associated with each tool for additional advice on individual objects.

8.5.2 **Defining Programs**

Note: Definition of Program Objects is optional and can be replaced directly with Job definitions. It is recommended that Program Objects be used for maximum reuse.

The first step in the process is to define each batch control as a Program object in the scheduler using the following attributes:

Attribute	Recommended content
program_name	Name of the Program. This name should not include any embedded characters or '-' character according to Oracle object naming conventions.
comments	A short description of the program. This is useful for searching the program.
enabled	Set to true to enable this program to be used by the scheduler.
program_type	Specify the PL/SQL Block as the type of program for the Oracle Scheduler Interface.
program_action	Specify the interface commands line for the execution. You may include any overrides, if desired, at this time. For optimization purpose, only specify the parameters that are not inherited from the global options or are not defaulted on the batch control. It is recommended to specify the Batch Control to avoid issues in submission.

Attribute	Recommended content	
	An example of a simple command line is:	
	begin OUAF_BATCH.Submit_Job(batch_code => 'BATCH01'); end;	

There are number of ways that can be used to specify the program using the various tools available:

Interface	Method of Definition
PL/SQL	Use the <u>DBMS_SCHEDULER.CREATE_PROGRAM</u> procedure using the above parameters to define the program object.
SQL Developer	Use the New Program menu item of the Scheduler tree to define the new program using a right click action on the Program node.
Enterprise Manager	Using the Administration → Oracle Scheduler → Programs menu item, specify the program information as above. Use the Source field to hold the PL/SQL command line for the interface.

You may create more than one program for the same batch control if there are different parameters is needed for different executions.

8.5.3 Defining Job Classes

Note: The use of <u>Job Classes</u> is optional. It is only used to group jobs for attribute inheritance, service affinity, monitoring purposes and/or resource profiling. **DEFAULT_JOB_CLASS** is used if no job class is specified. Job Class is only one technique for prioritizing jobs. Refer to <u>Prioritizing Jobs</u> for more information.

If <u>Job Classes</u> are to be used, they need to be setup to be used by the jobs allocated to them. The attributes of a Job Class are as follows:

Attribute	Recommended content
job_class_name	Name of the Job Class. This name should not include any embedded characters or '-' character according to Oracle object naming conventions.
comments	A short description of the job class. This is useful for searching for the job class.
resource_consumer_name	Name of the <u>resource consumer group</u> associated with jobs in this job class. Optional.
service	Name of database service associated with this job class name. Optional.
logging_level	Sets the level of logging is performed by the Oracle Scheduler. Optional.
log_history	Sets the retention period, in days, log history is retained by the Oracle Scheduler. Optional.

There are number of wa	vs that can be used to s	pecify the job class usin	g the various tools available:

Interface	Method of Definition
PL/SQL	Use the <u>DBMS_SCHEDULER.CREATE_JOB_CLASS</u> procedure using the above parameters to define the job class object.
SQL Developer	Use the New Job Class menu item of the Scheduler tree to define the new job class using a right click action on the Scheduler node.
Enterprise Manager	Using the Administration \rightarrow Oracle Scheduler \rightarrow Job Class menu item, specify the class information as above.

8.5.4 Defining Schedules

Note: This section is only a subset of the capabilities of the schedule object. For more advanced discussions and different scenarios refer to the <u>Creating and Managing Schedules to Define Jobs</u> in the Oracle Database documentation.

Before defining jobs and chains you may need to define a schedule to run them against. Schedules can be time based and/or event based. It is also possible to create multiple schedules to support complex scheduling requirements. For example, you can create a holiday schedule with the dates that are blacklisted for execution in another schedule.

The following attributes are typically populated for the schedule object:

Attribute	Recommended content
schedule_name	Name of the schedule. This name should not include any embedded characters or '-' character according to Oracle object naming conventions.
comments	A short description of the schedule. This is useful for searching the schedule.
start_date	Optional start date and time when the schedule becomes valid. If not populated, then the date jobs or windows are activated is used.
repeat_interval	This specifies how often the schedule repeats. It uses the <u>Calendaring Syntax</u> supported by the Oracle Scheduler. Even schedules decide the repeat interval for checking the event.
end_date	Optional date and time after jobs and windows allocated to this schedule will not execute.

There are number of ways that can be used to specify the schedule using the various tools available:

Interface	Method of Definition
PL/SQL	Use the <u>DBMS_SCHEDULER.CREATE_SCHEDULE</u> procedure using the above parameters to define the schedule object. This interface is recommended for complex <u>Calendaring Syntax</u> support.
SQL Developer	Use the New Credential menu item of the Scheduler tree to define the new schedule using a right click action on the Schedule node.

Interface	Method of Definition
Enterprise Manager	Using the Administration \rightarrow Oracle Scheduler \rightarrow Schedules menu item, specify the schedule information as above.

8.5.5 Defining Remote Destinations and Credentials

Note: This section outlines the process of specifying destinations and credentials for remote processing. If the database scheduler is housed within the product database (the default installation) then this section only applies to File Watcher type jobs.

In Oracle Database 12c, the **CREATE_CREDENTIAL** procedure for **DBMS_SCHEDULER** has been deprecated and replaced with the <u>CREATE_CREDENTIAL</u> procedure within the <u>DBMS_CREDENTIAL</u> package.

When executing Jobs and File Watchers that are remote from the scheduler database and location, it is required that a destination be defined for the job and relevant credentials for the job to execute on that destination. The following needs to be set up:

- To execute product jobs remotely, the product database server needs to be defined as a
 destination and the product database credentials should be specified. It is recommended that the
 values expressed in BATCH_DBUSER and BATCH_DBPASS be specified as credentials.
- For **File Watcher** jobs, the product server where the file is housed must be defined as a destination. The operating system credentials for the batch process must be specified to access the file must be specified as credentials.
- There is no explicit process for creating non-database related destinations in the API (there is no CREATE_AGENT_DESTINATION procedure). When an agent registers with the database scheduler as part of the startup procedure, it is automatically added as a destination. If you wish to register remote databases then use the CREATE DATABASE DESTINATION package.
- For <u>Database Destinations</u>, the database TNS information must exist on the scheduler database to connect remotely.
- At least one product related database destination must be registered for remote invocation of product jobs.
- The Oracle Scheduler agents must be executing for the scheduler to initiate and track remote jobs.

To specify the credentials the following attributes must be provided:

Attribute	Recommended content
credential_name	Name of the credential. This name should not include any embedded characters or '-' character according to Oracle object naming conventions.
comments	This attribute is not used by the DBMS_SCHEDULER package but can be provided for documentation purposes.
username	The userid to be used for connection. This attribute is required and is case sensitive.
password	The password associated with the username. This value is stored in obsfuscated format and is not available in Oracle Scheduler views.

Attribute	Recommended content
database_role	This is the database role associated with this user. This is not used for product jobs but is required for any DBA tasks requiring privilege access.
windows_domain	For Microsoft Windows Server implementations only. This is the windows domain for the user to connect to.

There are number of ways that can be used to specify the credentials using the various tools available:

Interface	Method of Definition
PL/SQL	Use the <u>DBMS_CREDENTIAL.CREATE_CREDENTIAL</u> procedure using the above parameters to define the credential object.
SQL Developer	Use the New Credential menu item of the Scheduler tree to define the new credential using a right click action on the Credentials node. Oracle SQL Developer uses DBMS_CREDENTIAL for credential management.
Enterprise Manager	Oracle Enterprise Manager uses its own security system for credentials. Refer to the <i>Enterprise Manager Cloud Control Security Guide</i> for more details.

When specifying <u>Database Destinations</u>, the following attributes need to be specified:

Attribute	Recommended content
destination_name	Name of the destination. This name should not include any embedded characters or '-' character according to Oracle object naming conventions.
comments	This attribute is not used by the DBMS_SCHEDULER package but can be provided for documentation purposes.
agent	The agent name as specified in the agent configuration file.
tns_name	Oracle service name as documented in the TNS file attached to the configuration file. This is used to connect from the scheduler database to the remote database.

There are number of ways that can be used to specify the database destination using the various tools available:

Interface	Method of Definition
PL/SQL	Use the <u>DBMS CREDENTIAL.CREATE DATABASE DESTINATION</u> procedure using the above parameters to define the credential object.
SQL Developer	Use the New Database Destination menu item of the Scheduler tree to define the new destination using a right click action on the Database Destinations node.

Interface	Method of Definition
Enterprise Manager	Oracle Enterprise Manager uses its own security system for destinations. Refer to the <i>Enterprise Manager Cloud Control Security Guide</i> for more details.

8.5.6 Defining Jobs

Points to Note:

This section is only a subset of the capabilities of the job object. For more advanced discussions refer to the <u>Jobs</u> section in the Oracle Database documentation.

Product jobs should never be defined as Lightweight jobs. Those are reserved for specific Oracle products.

The key object in the Oracle Scheduler is the Job object. This object is a collection of data that tells the scheduler what, when, where, and how to execute a particular process. In the case of the product, a job defines how to execute an instance of a Batch Control whether it is independent or part of a Chain.

Each Job definition has a set of attributes that define the Job:

Attribute	Recommended content
job_name	Name of the job. This name should not include any embedded characters or '-' character according to Oracle object naming conventions. It is recommended to replace '-' in Batch Controls with '_' to avoid naming issues.
comments	Description of Job. Useful for finding jobs.
job_type	If programs have been used, then the type STORED_PROCEDURE should be used. If programs are not used, then specify PLSQL_BLOCK with the action containing the source PL/SQL command.
job_action	Value depends on the specification of the job_type:
	 If job_type is STORED_PROCEDURE, then this will contain the fully qualified name of the program to execute.
	 If job_type is PLSQL_BLOCK, then this will contain the PL/SQL command to execute the OUAF_BATCH interface.
start_date	Optional start date and time when the schedule becomes valid. If not populated, then the date jobs or windows are activated is used. If schedule_name is specified, then this date and time may be null to inherit the value from the schedule or chain.
repeat_interval	Optional. Definition of how often the job will repeat. It uses the <u>Calendaring Syntax</u> supported by the Oracle Scheduler. Even schedules decide the repeat interval for checking the event. If <u>schedule_name</u> is specified, then this value may be null to inherit the value from the schedule or chain.
schedule_name	Optional. Name of schedule object dictating the schedule for this job.
job_class	Optional. Name of job class allocated to this job.

Attribute	Recommended content
end_date	Optional date and time after jobs and windows allocated to this job will not execute. If schedule_name is specified, then this date and time may be null to inherit the value from the schedule or chain.
credential_name	Optional. Name of credential to use for remote invocation for this job.
destination_name	Optional. Name of destination to use for remote invocation for this job. For remote product jobs this must be the location of the product database.
enabled	Whether this job is enabled or not. Only enabled jobs (true) are executed.
auto_drop	Whether after execution of this job, the job definition will be dropped. This is typically set to true for temporary jobs only. It is recommended to set to false for all regular product jobs.

There are additional attributes to manage the advanced features of the job. Refer to the <u>Job Object</u> for a discussion of the additional parameters.

There are number of ways that can be used to specify jobs using the various tools available:

Interface	Method of Definition
PL/SQL	Use the <u>DBMS_SCHEDULER.CREATE_JOB</u> procedure using the above parameters to define the job object.
SQL Developer	Use the New Job menu item of the Scheduler tree to define the new job using a right click action on the Jobs node.
Enterprise Manager	Using the Administration , Oracle Scheduler , Jobs menu item, specify the job information as above.

8.5.7 Defining Chains

Note: It is recommended to review the <u>Creating and Managing Job Chains</u> documentation for additional advice.

Once the jobs and schedule have been defined the next step is to define the set of job chains which configure the order and rules for a sequence of related jobs. Typically, a job chain represents a set of business-related processes that must be scheduled and processed in a specific order. For example, a nightly set of jobs that constitute a set of business processes is considered a chain.

There are various rules for a chain:

- There is a begin event and an end event that are automatically generated for a chain. The chain is considered ended when all jobs directly related to the end event are complete.
- Relationships in the chain are based upon job state events to dictate next actions. Typically, this is
 SUCCEEDED but can support other events. For example, it is possible to start the next job in a
 chain based upon a FAILED event to perform cleanup activities if required.

There are a number of key steps outlined in <u>Creating and Managing Job Chains</u> that should be performed with the following additions building chains that include product jobs:

- The naming conventions for the objects defined in the chain are subject to rules for all Oracle dictionary objects. It is recommended to prefix customizations with CM_ to avoid conflicts with base provided objects.
- It is recommended to implement a chain step per batch control that is applicable to the chain. The step name can match the Batch control or a valid alternative for your implementation.
- For each sequence in the chain, set the appropriate state in a Chain Rule for the setup. For example, if StepB must start only if StepA is complete then set the condition for the rule for Step A as "StepA SUCCEEDED" and action as "START StepB". Complex rules are supported. Refer to Adding Rules to a Chain for more details.

There are number of ways that can be used to specify chains using the various tools available:

Interface	Method of Definition
PL/SQL	Refer to <u>Creating and Managing Job Chains</u> for the sequence of statements to execute.
SQL Developer	Use the New Chain menu item of the Scheduler tree to define the new chain using a right click action on the Chains node.
Enterprise Manager	Using the Administration , Oracle Scheduler , Chains menu item, specify the chain information.

8.5.8 Other Scheduler Objects

There are several scheduler objects not covered in the above documentation that can be used by implementations using the following guidelines:

- <u>File Watchers</u> These objects create events based upon an arrival of a file in a configured location. To use File Watchers, a destination and credentials need to be defined along with the File Watcher itself. The file needs to be accessible by the process that is using it.
- <u>Windows</u> These are definitions of times and dates where certain conditions, restrictions, or resource profiles can be used. Oracle Scheduler supports discrete or overlapping Windows.

Note: Whilst supported, Oracle does not recommend overlapping windows.

 <u>Groups</u> - It is possible to group certain scheduler objects for efficient administration and clustering purposes.

8.5.9 Setting Preferences

One of the first steps in configuration is setting the preferences.

- The Oracle Scheduler includes several key preferences that need to be configured to ensure a
 consistent operation of the scheduler. These preferences are documented in the <u>Setting Scheduler</u>
 <u>Preferences</u> section of the <u>Oracle Scheduler Administration</u> documentation. It is recommended to
 set the preferences before using any of the functionality in the Oracle Scheduler.
- Once the Oracle Scheduler Interface is installed the GLOBAL options for the interface, should be set if they differ from the recommended defaults. This can be achieved using the <u>Set Option</u> (see <u>Set Option - Set a Global or Job Option</u>) procedure. At a minimum, it is recommended to set a global <u>user_id</u> to act as a default to avoid individual job issues.

 Optionally, it is possible to set Batch Job specific options using the Batch Control as the key for the <u>Set Option</u> (see <u>Set Option - Set a Global or Job Option</u>) procedure.

The above facilities set the overall scheduler and interface preferences.

8.5.10 Order of Preference

There are a number of different techniques available for setting the parameters for any job. The available techniques from lowest precedence to highest are as follows:

- **Batch Control** Job parameters can be set on the Batch Control record within the user interface under control of authorized users. This is commonly maintained by the business.
- Global Preferences Some of the parameters from the Batch Control can be specified as a
 GLOBAL preference using the <u>Set Option</u> (see <u>Set Option Set a Global or Job Option</u>)
 procedure. These preferences, if set, will override any Batch Control settings for the same setting.
- Batch Job Preferences The <u>Set_Option</u> (see <u>Set_Option</u> <u>Set a Global or Job Option</u>) procedure
 also supports the setting of parameters using the Batch Control as the key. Any overlapping
 settings set at this level will override settings on the Batch Control and any <u>GLOBAL</u> preference
 for the same setting.
- Command Line Options It is possible to override all settings using command line options on the Submit Job (see Submit Job Submit a Job or Thread) and Restart Thread (see Restart Thread Restart a Failed Thread/Job) procedures. This is handy for special processing. See Using soft_parm_map and Using soft_parm_list for advice and examples.

It is recommended to set the values in the relevant level and use command line options for special situations or when using dynamic parameters.

8.5.11 Using soft_parm_map

Batch parameters can be specified on the command line through the **soft_parm_map**, which is an <u>associative array</u>. This format can be used in isolation or in association with <u>soft_parm_list</u> (see <u>Using soft_parm_list</u>) when specifying command line parameters. When both are used, the <u>soft_parm_list</u> values are taken in precedence.

To use associative arrays, the array must be declared before use in the PL/SQL command.

Any array must be declared as type OUAF_BATCH.parm_map_t.

The format of soft parameter in an associate array is:

Segment	Format
Declaration of array	declare <arrayname> OUAF_BATCH.parm_map_t;</arrayname>
Definition of value	<arrayname>('<parmname>') := '<parmvalue>';</parmvalue></parmname></arrayname>
Use of map	soft_parm_map => <arrayname></arrayname>

Where:

Parameter	Description
<arrayname></arrayname>	Name of associative array to be used as the soft_parm_map

<parmname></parmname>	Name of the parameter to be set
<parmvalue></parmvalue>	Value of parameter

For example:

```
declare
```

```
my_soft_parms OUAF_BATCH.parm_map_t;
begin
    my_soft_parms('maintenanceObject') := 'F1-SYNC REQ';
    my_soft_parms('isRestrictedByBatchCode') := 'true';
    OUAF_BATCH.Submit_Job(batch_code => 'F1-SYNRQ', user_id => 'FRED01', soft_parm_map => my_soft_parms);
end;
```

The my_soft_parms is the soft_parm_map in the above example. The use of associative arrays is a way of supporting dynamic parameters for complex parameters. This technique can be used exclusively or in conjunction with soft parm list.

Note: The associative array should not contain common parameters such as business_date, user_id, and so on.

8.5.12 Using soft_parm_list

An alternative to the <u>soft_parm_map</u> (see <u>Using soft_parm_map</u>) is to explicitly specify the parameters as a list of parameter and value pairs. This method is recommended for explicit values for the parameters. The parameter list must be of type **OUAF BATCH.parm_list_t**.

The parameters are specified in the following format:

OUAF BATCH.parm list t('<parmname>','<parmvalue>'...)

Where:

Parameter	Description
<pre><parmname></parmname></pre>	Name of the parameter to be set
<pre><parmvalue></parmvalue></pre>	Value of parameter

For example:

```
begin
```

```
OUAF_BATCH.Submit_Job(batch_code => 'F1-SYNRQ', user_id => 'SYSUSER', soft_parm_list => OUAF_BATCH.parm_list_t('maintenanceObject','F1-SYNC REQ', 'isRestrictedByBatchCode','true'));
```

end;

This technique can be used exclusively or in conjunction with soft parm map.

Note: The array should not contain common parameters such as business_date, user_id, and so on.

8.6 Oracle Scheduler – REST APIs

The below are the list of services that can be used for managing Oracle DBMS scheduler objects:

- 1. **F1-DBMSProgram Service**: The **F1-DBMSProgram** service can be used to add, read, change, and delete a DBMS Scheduler Program object. There are currently two types of programs that can be created:
 - Program associated with a batch code
 - Program to set/unset options
 - If a list of options is provided, it will create a program to set/unset options. Otherwise, it will create a program associated with a batch code.

Parameter Name	Description
Action	Specifies the action to be performed on the scheduler object.
	Valid values are:
	ADD – Add
	READ – Read
	CHNG – Change
	DEL – Delete
Name	The name of the scheduler program on which the operation needs to be performed.
description	Description of the scheduler program.
batchCode	Batch code of the OUAF batch process for which the program is being created.
userld	ID under which the batch process will run.
threadCount	Use Thread Count to control whether a background process is run single threaded or in multiple parallel threads. This value defines the total number of threads that have been scheduled
businessDate	Process date to be used for batch job. If no value is provided, the current date will be used. The format of the date must be in a recognizable format.
maxTimeoutMins	Maximum timeout, in minutes, for transactions to avoid ORA-01555 Snapshot too old errors. Default is 15.
rerunNumber	Is only used for OUAF background processes that download information that belongs to given run number. It should only be supplied if you need to download an historical run (rather than the latest run).
threadPool	The default threadpool to use. The installation default threadpool is 'DEFAULT'.

Parameter Name	Description
minRunStatus	Minimum Run Status that will cause this procedure to exit. The default is RUN_STAT_COMPLETED (40). Other values supported:
	10 - RUN_STAT_PENDING
	20 - RUN_STAT_IN_PROGRESS
	30 - RUN_STAT_ERROR
	40 - RUN_STAT_COMPLETED
raiseError	If the min_run_status is set a value less than 40, this parameter is set to true, and the job status matches the value of the min_run_status then raise an application error. This allows the chain to support conditional branches or stop chains on conditions. Default is false.
threadNotifications	Whether if an error in any thread should trigger a notification event. Default is true. See Notification Options for more information.
parmName	The name of the parameter to the OUAF batch process, if applicable.
(List parameter)	
parmValue	The corresponding value of the parameter to the OUAF batch process, if
(List parameter)	applicable. parmValue and parmName pairs should be defined in repeated lists.
optionName	Option name to set/unset before program is executed
(List parameter)	
optionScope	Corresponding scope for the options to set/unset before program is
(List parameter)	executed. The scope can be global or per batch code.
optionValue	Corresponding value for the option name.
(List parameter)	

2. **F1-DBMSChain Service**: The **F1-DBMSChain** service provides the ability to add, read, change, or delete a DBMS Scheduler Chain object based on the action provided.

Parameter Name	Description
action	Sepcifies the action to be performed on the scheduler object. Valid values are: • ADD – Add • READ – Read • CHNG – Change • DEL – Delete
name	The name of the scheduler chain on which the operation needs to be performed.
description	Description of the scheduler chain.

Parameter Name	Description
stepName (list parameter)	The name of the step within the scheduler chain.
programName (list parameter)	The program name that is part of the corresponding step.
condition (list parameter)	A condition that must be met to complete the step and to transition to the next step or to end the chain execution.

Note: A step called 'END' step must be included in the chain definition that includes the condition to meet for the chain to end.

3. **F1-DBMSScheule Service**: The **F1-DBMSScheule** service allows the ability to add, read, change, or delete a DBMS Scheduler's schedule object based on the action provided.

Parameter Name	Description	
action	Sepcifies the action to be performed on the scheduler object.	
	Valid values are:	
	ADD – Add	
	READ – Read	
	CHNG – Change	
	DEL – Delete	
name	The name of the scheduler's schedule object being created/edited/read/deleted.	
description	Description of the schedule.	
repeatInterval	The schedule's repeat interval to be specified in the format supported by Oracle DBMS Scheduler. (Refer to the Oracle DBMS scheduler's documentation).	

- 4. **F1-DBMSJob Service**: The **F1-DBMSJob Service** provides the ability to add, read, change, or delete a DBMS Scheduler's job object based on the action provided.
 - The job can be associated with either a program or a chain by populating the appropriate field. A validation error will result if both or neither of the fields are populated.
 - If schedule name is not populated, it will be for immediate execution.
 - When called for change action, the job is added if it does not exist, else it is replaced with new definition.

Parameter Name	Description	
action	Sepcifies the action to be performed on the scheduler object.	
	Valid values are:	
	ADD – Add	
	READ – Read	
	CHNG – Change	
	DEL – Delete	
name	The name of the scheduler's job object being created/edited/read/deleted.	
description	Description of the scheduler's job object.	
programName	The name of the scheduler's program to which this job should be associated with.	
chainName	The name of the scheduler's chain to which this job should be associated with.	
scheduleName	The name to the schedule's schedule object based on which this job needs to be executed.	
enabled	Specified if this job should be enabled or disabled.	

5. **F1-DBMSJOB Service**: This service returns a list of name and descriptions of DBMS Scheduler objects based on the type and name (if specified) provided.

Parameter Name	Description
type	Specifies the type of scheduler object whose list is to be retrieved. Valid values are:
	PROG – DBMS Scheduler Program
	CHAN – DBMS Scheduler Chain
	SCHD – DBMS Scheduler Schedule
	JOB – DBMS Scheduler Job
name	Name to search with. Appending '%' to the end of name will perform a 'like' query resulting in a list of objects starting with the name provided.

6. **F1-DBMSSubmitJob Service**: The **F1-DBMSSubmitJob** service submits a scheduler job for execution.

Parameter Name	Description
name	Name of the scheduler's job object to be submitted for execution.

7. **F1-DBMSGetJobDetails Service**: The **F1-DBMSGetJobDetails** service retrieves the details of DBMS Scheduler job based on job name. More specifically, this retrieves the steps and the step state of the DBMS scheduler job.

Parameter Name	Description
name	Name of the scheduler's job object whose details are to retrieved/read.
Status	Status of the DBMS scheduler job.
startDate	The start date of the DBMS scheduler job.
runDuration	The run duration of the DBMS scheduler job.
stepName (List parameter of "steps" list)	The name of the DBMS Scheduler job's step.
status (List parameter of "steps" list)	The status of the corresponding step.
runDuration	The run duration of the corresponding step.

8. **F1-DBMSGetJobs Service**: The **F1-DBMSGetJobs** service retrieves a list of scheduler jobs based on the status of RUNNING or COMPLETED. A date range can be specified to limit the list.

Note: The maximum numbers of records returned for completed jobs is 100.

This retrieves the list of jobs for COMPLETED jobs, list of jobs with steps for RUNNING chains.

The following criteria (from top to bottom) is considered for determining if a job run is IN PROGRESS, or if it is COMPLETED:

- If a DBMS job run has at least one step running, the job is considered as IN PROGRESS.
- If at least one step has failed, it is considered COMPLETED.
- If at least one step has not been started, and no steps have failed, it is considered IN PROGRESS.
- If none of the above is true (that is, if all steps are completed), it is considered COMPLETED.

Parameter Name	Description
jobStatus	The status based on which the list of DBMS scheduler jobs list has to be retrieved.
	Valid values are:
	RUN – Running Jobs
	COMP – Completed Jobs
startDate	The start date of the date range for which the details have to be retrieved.
endDate	The end date of the date range for which the details have to be retrieved.
jobStatus	The status of the job.
(List parameter of "jobs" list)	
runDate	The execution date of the corresponding job.
(List parameter of "jobs" list)	

Parameter Name	Description
runDuration	The run duration of the corresponding job.
(List parameter of "jobs" list)	
chainName	The name of the associated chain (if applicable).
(List parameter of "jobs" list)	
stepName	The name of the chain step within the job.
(List parameter of "steps" list)	
stepState	The state of the corresponding step.
(List parameter of "steps" list)	
batchCode	The batch code of the corresponding step.
(List parameter of "steps" list)	
batchNumber	The batch number of the corresponding step.
(List parameter of "steps" list)	
batchRerunNumber	The batch rerun number of the corresponding step.
(List parameter of "steps" list)	
ErrorDetails	The error corresponding to the step (if applicable).
(List parameter of "steps" list)	

9. **F1-DBMSCancelJob Service**: The **F1-DBMSCancelJob** service cancels a DBMS schedule job if it is running.

Parameter Name	Description
name	The name of the DBMS scheduler job to cancel.

10. **F1-DBMSRestartThread Service**: The **F1-DBMSRestartThread** service can be used for restarting a failed batch thread.

Parameter Name	Description
batchCode	Batch code of the OUAF batch process for which the failed thread needs to be restarted.
userld	User ID of the user using which the batch thread needs to be restarted.
threadNumber	The thread number of the batch program that needs to be restarted.
threadCount	Use Thread Count to control whether a background process is run single threaded or in multiple parallel threads. This value defines the total number of threads that have been scheduled
businessDate	Process date to be used for batch job. If no value is provided, the current date will be used. The format of the date must be in a recognizable format.

Parameter Name	Description
maxTimeoutMins	Maximum timeout, in minutes, for transactions to avoid ORA-01555 Snapshot too old errors. Default is 15.
rerunNumber	Is only used for OUAF background processes that download information that belongs to given run number. It should only be supplied if you need to download an historical run (rather than the latest run).
threadPool	The default threadpool to use. The installation default threadpool is 'DEFAULT'.
parmName (list parameter)	The name of the parameter to the OUAF batch process, if applicable.
parmValue (list parameter)	The corresponding value of the parameter to the OUAF batch process, if applicable. parmValue and parmName pairs should be defined in repeated lists.

11. **F1-DBMSRestartChain Service**: The **F1-DBMSRestartChain** service can be used to restart DBMS scheduler Chain. The service determines the failed step and changes status so the chain can resume.

Parameter	Description
jobName	The name of the DBMS scheduler job to cancel.

8.7 Executing Jobs

There are several techniques that can be used to execute a schedule and/or a job. The following techniques can be used:

- Chains can be executed using a predefined schedule or manually started by starting the job created for the chain. Refer to <u>Running Jobs</u> for additional information.
- Events can trigger jobs when the event occurs. Refer to <u>Using Events to Start Jobs</u> for more information.

Chains and Jobs that are enabled are only executed.

8.8 Monitoring Oracle Scheduler

There are various techniques available from the interface and related tools to monitor Oracle Scheduler. Refer to Monitoring Jobs for additional advice.

Note: Any product job can also be monitored using the Batch Run Tree, JMX interface or through the Oracle Utilities Batch Server target page within Oracle Enterprise Manager through the Application Management Pack for Oracle Utilities.

8.8.1 Job States

When any job is waiting to be executed, executing, completed or errored the scheduler updates the state of the job in its job tables. These states are available from the tools mentioned earlier in various forms. The states that are raised are documented in Monitoring Job State with Events Raised by the Scheduler.

8.8.2 Dictionary Views

The most common technique for monitoring the scheduler itself is the provided <u>Scheduler Data Dictionary Views</u>. These views not only provide details of the Oracle Scheduler Objects but can provide execution information. There are two views that are of particular interest for executions:

- *_SCHEDULER_RUNNING_CHAINS Show all chains that have active jobs.
- *_SCHEDULER_RUNNING_JOBS Show state information for all jobs running at present.

These views are accessible from any SQL product or through Oracle Enterprise Manager through the **Administration**, **Oracle Scheduler**, **Home** menu item on the database target used by the Oracle Scheduler.

8.8.3 Scheduler Notifications

One of the features of the Oracle Scheduler is that it is possible to send an email based upon the state of a job within the scheduler. This is based upon the state of the job and the email format can be customized based upon the state. For more information and examples of the capability refer to Monitoring Job State with E-mail Notifications.

The Oracle Scheduler Interface includes the **OUAF_NOTIFY** job that can be used as a template.

8.9 Cancellation

Once a job has been executed there are two techniques for cancelling a running job or thread:

- Use the <u>OUAF_BATCH.Cancel_Job</u> API (see <u>Cancel_Job Cancel a Running Job</u>) to stop the thread or job. The job state will be set to <u>STOPPED</u>.
- Use the <u>Batch JMX API</u> (see <u>Batch JMX Reference</u>) to cancel a thread.

The cancellation will be registered on the batch run tree including any relevant security information for auditing purposes.

8.10 Exporting Schedules Across Environments

As the schedule is a set of dictionary objects it can be exported and imported using any of the Oracle database copy, cloning or exporting functions. Utilities such as **exp** or **expdp** can be used to export the schema of the owner of the schedule.

It is also possible to isolate the scheduler objects using the data pump **INCLUDE** function. The **INCLUDE** statement should use the following filter:

INCLUDE=procobj:"IN (SELECT NAME FROM sys.OBJ\$ WHERE TYPE# IN (47, 48, 66, 67, 68, 69, 71, 72, 74))"

For example:

expdp <user>/<password> DIRECTORY=<directory> DUMPFILE=<expfile> LOGFILE=<logfile> SCHEMAS=<schema> INCLUDE=procobj:"IN (SELECT NAME FROM sys.OBJ\$ WHERE TYPE# IN (47, 48, 66, 67, 68, 69, 71, 72, 74))"

Appendix A: Parameters

This section contains the name, description, and details of both mandatory and optional parameters available for the Oracle Utilities Application Framework Server Administration Guide, version 4.5.0.1.1.

A.1 Conventions Used in This Section

This section contains several conventions to illustrate attributes and scope of configuration parameters:

- Each parameter has certain valid values. When applicable, the default value is indicated in bold.
- The scope of the parameter is indicated through the following terms for the applicable tiers:

Tier	Description
WEB	Web Application Server
BAS	Business Application Server
IWS	Inbound Web Services
DB	Database
BATCH	Background Processing

• The ordinality of the parameter is indicated. Parameters that are mandatory must exist and are set in the relevant configuration file for the product to operate.

A.2 ENVIRON.INI

The <u>ENVIRON.INI</u> is the environment file that is output from <u>configureEnv</u> and is used by <u>initialSetup</u> to build the configuration files from templates. See <u>ENVIRON.INI</u> - <u>Environment Configuration File</u>, configureEnv - Set up Environment Settings, and initialSetup - Maintain Configuration Settings for details.

A.2.1 ALLOW_SELFSIGNED_SSL – Enable Self Signed SSL

Parameter	ALLOW_SELFSIGNED_SSL
Description	Specifies if self-signed SSL is allowed
Ordinality	Mandatory
Valid Values	[true false]
Tier	Web Application Server, Business Application Server

A.2.2 ANT_ADDITIONAL_OPT - Additional Options for ANT

Parameter	ANT_ADDITIONAL_OPT
Description	Implementation specific options for WAR and EAR builds used by starttpw.sh - Start Threadpoolworker.
Ordinality	Optional
Valid Values	Valid ANT options
Tier	Web Application Server, Business Application Server, Inbound Web Services, Background Processing

A.2.3 ANT_HOME - Location of ANT

Parameter	ANT_HOME
Description	Generated location of ANT used by <u>starttpw.sh</u> - <u>Start Threadpoolworker</u> . This value is auto generated and should not be altered.
Ordinality	Mandatory
Valid Values	Valid location of ANT
Tier	Web Application Server, Business Application Server, Inbound Web Services, Background Processing

A.2.4 ANT_OPT_MAX - ANT Maximum Heap Size

Parameter	ANT_OPT_MAX
Description	Maximum memory in MB allocated to ANT builds. Unless otherwise instructed by Oracle Support this value should not be altered.
Ordinality	Optional
Valid Values	Default: 800
Tier	Web Application Server, Business Application Server, Inbound Web Services, Background Processing

A.2.5 ANT_OPT_MIN - ANT Minimum Heap Size

Parameter	ANT_OPT_MIN
Description	Minimum memory in MB allocated to ANT builds. Unless otherwise instructed by Oracle Support this value should not be altered.
Ordinality	Optional
Valid Values	Default: 200
Tier	Web Application Server, Business Application Server, Inbound Web Services, Background Processing

A.2.6 BATCHDAEMON - Whether Online Batch Daemon is Enabled

Parameter	BATCHDAEMON
Description	Whether the Online Batch Daemon is enabled or not.
Ordinality	Mandatory
Valid Values	[true false]
Tier	Business Application Server, Background Processing

A.2.7 BATCHEDIT_ENABLED - Whether Batch Edit Facility is Enabled

Parameter	BATCHEDIT_ENABLED
Description	Whether the Batch Edit facility is enabled or not.
Ordinality	Mandatory
Valid Values	[true false]
Tier	Background Processing

A.2.8 BATCHENABLED - Whether Online Batch Server is Enabled

Parameter	BATCHENABLED
Description	Whether the Online Batch Server is enabled or not.
Ordinality	Mandatory
Valid Values	[true false]
Tier	Business Application Server, Background Processing

A.2.9 BATCHTHREADS - Number of Online Batch Server Threads

Parameter	BATCHTHREADS
Description	Number of Threads in DEFAULT online threadpool.
Ordinality	Mandatory
Valid Values	Default: 5
Tier	Business Application Server

A.2.10 BATCH_DBPASS - Batch User Password

Parameter	BATCH_DBPASS
Description	Encrypted password for database user used for batch.
Ordinality	Mandatory
Valid Values	Encrypted password
Tier	Background Processing, Database

A.2.11 BATCH_DBUSER - Batch User

Parameter	BATCH_DBUSER
Description	Database user used for batch.
Ordinality	Mandatory
Valid Values	Valid database user
Tier	Background Processing, Database

A.2.12 BATCH_MEMORY_ADDITIONAL_OPT - Threadpool Worker JVM Additional Options

Parameter	BATCH_MEMORY_ADDITIONAL_OPT
Description	Additional JVM Options for Threadpools
Ordinality	Mandatory
Valid Values	Valid Threadpool parameters. Example: BATCH_MEMORY_ADDITIONAL_OPT=-Xdebug -Xnoagent - Xrunjdwp:transport=dt_socket,address=7757, server=y,suspend=n -Djava.compiler=NONE
Tier	Background Processing

A.2.13 BATCH_MEMORY_OPT_MAX - Threadpool Worker Java Maximum Heap Size

Parameter	BATCH_MEMORY_OPT_MAX
Description	Maximum JVM Memory for each Threadpool instance
Ordinality	Mandatory
Valid Values	Memory specification (in MB). Default: 1024
Tier	Background Processing

A.2.14 BATCH_MEMORY_OPT_MIN - Threadpool Worker Java Minimum Heap Size

Parameter	BATCH_MEMORY_OPT_MIN
Description	Minimum JVM Memory for each Threadpool instance
Ordinality	Mandatory
Valid Values	Memory specification (in MB). Default: 512
Tier	Background Processing

A.2.15 BATCH_MODE - Default Mode of Batch

Parameter	BATCH_MODE
Description	Batch Execution Mode for Threadpools
Ordinality	Mandatory
Valid Values	[THIN CLUSTERED]
Tier	Background Processing

A.2.16 BATCH_ONLINE_LOG_DIR - Online Batch Submission Log Directory

Parameter	BATCH_ONLINE_LOG_DIR
Description	Location of Online Batch Submission logs
Ordinality	Optional
Valid Values	Valid directory
Tier	Business Application Server

A.2.17 BATCH_RMI_PORT - RMI Port for Batch

Parameter	BATCH_RMI_PORT
Description	Port number used for communication to Threadpools. This is used for JMX monitoring.
Ordinality	Mandatory
Valid Values	Valid Port Number
Tier	Background Processing

A.2.18 BSN_APP - Business Server Application Name

Parameter	BSN_APP
Description	Deployed Business Application Server Name
Ordinality	Mandatory
Valid Values	Default: SPLService
Tier	Business Application Server

A.2.19 BSN_JMX_RMI_PORT_PERFORMANCE - JMX Port for Business Application Server

Parameter	BSN_JMX_RMI_PORT_PERFORMANCE
Description	JMX Port for business application server monitoring
Ordinality	Optional
Valid Values	Valid open port for JMX
Tier	Business Application Server

A.2.20 BSN_JMX_SYSPASS - Password for BAS JMX Monitoring

Parameter	BSN_JMX_SYSPASS
Description	Default encrypted password for JMX monitoring of business application server Name for BSN_JMX_SYSUSER. This is required if BSN_JMX_RMI_PORT_PERFORMANCE is set.
Ordinality	Optional
Valid Values	Encrypted Password
Tier	Business Application Server

A.2.21 BSN_JMX_SYSUSER - Default User for BSN JMX Monitoring

Parameter	BSN_JMX_SYSUSER
Description	Default user for JMX monitoring of business application server name. This is required if BSN_JMX_RMI_PORT_PERFORMANCE is set.
Ordinality	Optional
Valid Values	Administration User
Tier	Business Application Server

A.2.22 BSN_NODENAME - IBM WebSphere Node Name

Parameter	BSN_NODENAME
Description	IBM WebSphere Node to deploy business application server to.
Ordinality	Mandatory
Valid Values	Valid IBM WebSphere Node Names
JEE Web Application Server	IBM WebSphere Application Server, IBM WebSphere Application Server Network Deployment
Tier	Business Application Server

A.2.23 BSN_SVRNAME - IBM WebSphere Server Name

Parameter	BSN_SVRNAME
Description	IBM WebSphere Server Name used to deploy business application server to.
Ordinality	Mandatory
Valid Values	Valid IBM WebSphere Server Names
JEE Web Application Server	IBM WebSphere Application Server, IBM WebSphere Application Server Network Deployment
Tier	Business Application Server

A.2.24 BSN_WASBOOTSTRAPPORT - Bootstrap Port

Parameter	BSN_WASBOOTSTARPPORT
Description	IBM WebSphere Server Bootstrap Port used for business application server.
Ordinality	Mandatory
Valid Values	Valid IBM WebSphere Bootstrap Ports
JEE Web Application Server	IBM WebSphere Application Server, IBM WebSphere Application Server Network Deployment
Tier	Business Application Server

A.2.25 BSN_WLHOST - Bootstrap Host

Parameter	BSN_WLHOST
Description	Oracle WebLogic host name for business application server. For native and/or clustered installations this setting should be set to localhost.
Ordinality	Mandatory
Valid Values	Default: Current Host Name
Tier	Business Application Server

A.2.26 BSN_WLHOST - Business App Server Host

Parameter	BSN_WLHOST
Description	Oracle WebLogic host name for business application server. For native and/or clustered installations this setting should be set to localhost.
Ordinality	Mandatory
Valid Values	Default: Current Host Name
Tier	Business Application Server

A.2.27 CALC_WLS_COMMON_JAR_DIR – Weblogic's Jersey Jars Directory

Parameter	CALC_WLS_COMMON_JAR_DIR
Description	The full path to the jersey Jars in weblogic install directory.
Ordinality	Mandatory
Valid Values	Full path
Tier	Web Application Server, Business Application Server, Background Processing

A.2.28 CALC_WLS_SERVER_JAR_DIR – Weblogic Server Lib Jars Directory

Parameter	CALC_WLS_SERVER_JAR_DIR
Description	The full path to the weblogic server lib Jars in weblogic install directory.
Ordinality	Mandatory
Valid Values	Full path
Tier	Web Application Server, Business Application Server, Background Processing

A.2.29 CHAR_BASED_DB - Specifies If the DB Is Char-Based

Parameter	CHAR_BASED_DB
Description	Specifies if the DB is char based.
Ordinality	Mandatory
Valid Values	[true false]
Tier	Web Application Server, Business Application Server, Background Processing

A.2.30 CLOUD_CUSTOM_WHITE_LIST_PATH – Custom URL Allow Lists for Cloud

Parameter	CLOUD_CUSTOM_WHITE_LIST_PATH
Description	The full path to a custom allow list for aliases for URLs within the product. This allow list is added to the base product allow list which is provided in CLOUD_WHITE_LIST_PATH variable. This is primarily for cloud implementations to define URL aliases. See support for host allow listing.
Ordinality	Optional
Valid Values	Full path (including filename to allow list)
Tier	Web Application Server, Business Application Server, Background Processing

A.2.31 CLOUD_LOCATION_F1_BASE_IWS_URI – URI for Variable F1_BASE_IWS_URI

Parameter	CLOUD_LOCATION_F1_BASE_IWS_URL
Description	The base WSDL URI is different than the application server URI and must be configured for cloud implementations. Need not be configured for on-premise implementations.
Ordinality	Optional
Valid Values	Full path
Tier	Web Application Server, Business Application Server

A.2.32 CLOUD_LOCATION_F1_BASE_REST_URL - URI for Variable F1_BASE_REST_URL

Parameter	CLOUD_LOCATION_F1_BASE_REST_URL
Description	URI for variable F1_BASE_REST_URL. This is for implementations to define the base URI for REST. This is primarily for cloud implementations.
Ordinality	Optional
Valid Values	Full path
Tier	Web Application Server, Business Application Server

A.2.33 CLOUD_LOCATION_F1_BASE_WEB_URI – URI for Variable F1_BASE_WEB_URI

Parameter	CLOUD_LOCATION_F1_BASE_WEB_URI
Description	The environment URL used to launch the application server from an external link must be configured for cloud implementations. Need not be configured for on-premise implementations.
Ordinality	Optional
Valid Values	Full path
Tier	Web Application Server, Business Application Server

A.2.34 CLOUD_LOCATION_F1_MIGR_ASSISTANT_FILES – Location of CMA Files for Migrations

Parameter	CLOUD_LOCATION_F1_MIGR_ASSISTANT_FILES
Description	The full path to the location of the CMA files for content migration. This is primarily for cloud implementations to define configuration file location for CMA process.
Ordinality	Optional
Valid Values	Full path
Tier	Web Application Server, Business Application Server, Background Processing.

A.2.35 CLOUD_LOCATION_F1_OAUTH2_URI – URI for OAUTH2

Parameter	CLOUD_LOCATION_F1_OAUTH2_URI
Description	The URI for implementing OAUTH2.
	This is primarily for cloud implementations to implement OAUTH2.
Ordinality	Optional
Valid Values	Full URI
Tier	Web Application Server, Business Application Server, Background Processing

A.2.36 CLOUD_LOCATION_F1_OPEN_API_BASE_URL - URI for variable F1_OPEN_API_BASE_URL

Parameter	CLOUD_LOCATION_F1_OPEN_API_BASE_URL
Description	URI for variable F1_OPEN_API_BASE_URL. This is for implementations to define the base URI for Open API. This is primarily for cloud implementations.
Ordinality	Optional
Valid Values	Full path
Tier	Business Application Server

A.2.37 CLOUD_RESTRICTIONS_URLS_ENABLE - Enable or Disable URL Restrictions

Parameter	CLOUD_RESTRICTIONS_URL_ENABLE
Description	Whether the allow lists for URL's are enabled. This is primarily for cloud implementations.
Ordinality	Optional
Valid Values	[true false]
Tier	Web Application Server, Business Application Server, Background Processing

A.2.38 CLOUD_SUBSTITUTION_VARIABLE_LIST_FILE_LOCATI ON - Enable or Disable URL Restrictions

Parameter	CLOUD_SUBSTITUTION_VARIABLE_LIST_FILE_LOCATION
Description	Points to the file containing the predefined URI substitution variable list. This is primarily for cloud implementations
Ordinality	Optional [Mandatory only for Cloud implementations]
Valid Values	Full Path (including the filename for substitution list)
Tier	Web Application Server, Business Application Server, Background Processing

A.2.39 CLOUD_WHITE_LIST_PATH - URL Allow Lists for Cloud

Parameter	CLOUD_WHITE_LIST_PATH
Description	The full path to a base allow list for aliases for URLs within the product. This allow list is added with the custom product allow list which is provided in CLOUD_CUSTOM_WHITE_LIST_PATH variable.
	This is primarily for cloud implementations to define <u>URL aliases</u> . See Support for host allow listing.
Ordinality	Optional
Valid Values	Full path (including filename to allow list)
Tier	Web Application Server, Business Application Server, Background Processing

A.2.40 CMPDB - Database Type

Parameter	CMPDB
Description	Database Type. This parameter is provided for backward compatibility and is set to ORACLE .
	This should not be altered.
Ordinality	Mandatory
Valid Values	ORACLE
Tier	Business Application Server, Background Processing

A.2.41 CM_INSTALL_SAMPLE - Whether samples are installed

Parameter	CM_INSTALL_SAMPLE
Description	Whether sample code is installed or not. This is done at installation time.
Ordinality	Mandatory
Valid Values	[true false]
Tier	Web Application Server, Business Application Server, Background Processing

A.2.42 COHERENCE_CLUSTER_ADDRESS - Multicast address for Batch Cluster

Parameter	COHERENCE_CLUSTER_ADDRESS
Description	Multicast IP Address for CLUSTERED mode. Specify the multicast IP address that a Socket will listen or publish on.
Ordinality	Mandatory
Valid Values	Valid values are from 224.0.0.0 to 239.255.255.
Tier	Background Processing

A.2.43 COHERENCE_CLUSTER_MODE - Batch Cluster Mode

Parameter	COHERENCE_CLUSTER_MODE
Description	Oracle Coherence mode. Coherence may be configured to operate in either development or production mode. These modes do not limit access to features, but instead alter some default configuration settings. For instance, development mode allows for faster cluster startup to ease the development process.
	The development mode is used for all pre-production activities, such as development and testing. This is an important safety feature because development nodes are restricted from joining with production nodes. Development mode (dev) is the default mode. Production mode (prod) must be explicitly specified when using Coherence in a production environment.
Ordinality	Mandatory
Valid Values	[dev prod]
Tier	Background Processing

A.2.44 COHERENCE_CLUSTER_NAME - Batch Cluster Name

Parameter	COHERENCE_CLUSTER_NAME
Description	Unique Cache name for Coherence Clusters.
Ordinality	Mandatory
Valid Values	Any string value. It is recommended to use the SPLENVIRON value, optionally, with the database schema owner as a unique identifier. Example: DEV.SPLADM
Tier	

A.2.45 COHERENCE_CLUSTER_PORT - Batch Cluster Port Number

Parameter	COHERENCE_CLUSTER_PORT
Description	Unique Cache port for the Coherence Cluster.
Ordinality	Mandatory
JEE Web Application Server	Not applicable
Valid Values	Any open relevant port unique to the COHERENCE_CLUSTER_NAME.
Tier	Background Processing
Installation Mode	Not applicable

A.2.46 CONSOLIDATED_LOG_FILE_PATH – Directory for Consolidated Log File

Parameter	CONSOLIDATED_LOG_FILE_PATH
Description	Specifies the directory for the consolidated log file.
Ordinality	Optional
Valid Values	Full directory path.
Tier	Web Application Server, Business Application Server, Background Processing, Database

A.2.47 CSP_CONNECT_SRC - Custom URI for Content Security Policy connect-src

Parameter	CSP_CONNECT_SRC
Description	Specifies a custom URI for the connect-src directive of Custom-Security-Policy.
Ordinality	Optional
Valid Values	Full URI.
Tier	Web Application Server

A.2.48 CSP_FONT_SRC - Custom URI for Content Security Policy font-src

Parameter	CSP_FONT_SRC
Description	Specifies a valid URI for font-src directive in Custom-Security-Policy.
Ordinality	Optional
Valid Values	Full URI.
Tier	Web Application Server

A.2.49 CSP_STYLE_SRC - Custom URI for Content Security Policy style-src

Parameter	CSP_STYLE_SRC
Description	Specifies a valid URI for style-src directive in Custom-Security-Policy.
Ordinality	Optional
Valid Values	Full URI.
Tier	Web Application Server

A.2.50 CSP_URL_IMG_SRC - Custom URI for Content Security Policy img-src

Parameter	CSP_URL_IMG_SRC
Description	Specifies a valid URI for img-src directive in Custom-Security-Policy.
Ordinality	Optional
Valid Values	Full URI.
Tier	Web Application Server

A.2.51 CSP_URL_SCRIPT_SRC - Custom URI for Content Security Policy script-src

Parameter	CSP_URL_SCRIPT_SRC
Description	Specifies a valid URI for script-src directive in Custom-Security-Policy.
Ordinality	Optional
Valid Values	Full URI.
Tier	Web Application Server

A.2.52 CORS_ALLOWED_FRAME_ANCESTORS_MAX_NUMB ER - Maximum Number of Frame Ancestors

Parameter	CORS_ALLOWED_FRAME_ANCESTORS_MAX_NUMBER
Description	This specifies the maximum number of frame ancestors for Cross Origin Resource Sharing source host if ENABLE_CORS is set to true.
Ordinality	Optional
Valid Values	Number of ancestors
Tier	Web Application Server

A.2.53 CORS_ALM_DOMAIN - URI for Variable ALM_DOMAIN

Parameter	CORS_ALM_DOMAIN
Description	URI for substitution variable FA_DOMAIN for setting secure redirect in development for Cross Origin Resource Sharing.
Ordinality	Optional. May be needed only if CORS for embedded UI is true.
Valid Values	URI
Tier	Web Application Server

A.2.54 CORS_CSP_FRAME_ANCESTOR_HOST1 - URI for Substitution Variable CSP_FRAME_ANS_HOST1

Parameter	CORS_CSP_FRAME_ANCESTOR_HOST1
Description	URI for substitution variable CSP_FRAME_ANS_HOST1. Allowed frame ancestor.
Ordinality	Optional. Required only if CORS for embedded UI is true.
Valid Values	URI
Tier	Web Application Server

A.2.55 CORS_CSP_FRAME_ANCESTOR_HOST2 - URI for Substitution Variable CSP_FRAME_ANS_HOST2

Parameter	CORS_CSP_FRAME_ANCESTOR_HOST2
Description	URI for substitution variable CSP_FRAME_ANS_HOST2. Allowed frame ancestor.
Ordinality	Optional. Required only if CORS for embedded UI is true.
Valid Values	URI
Tier	Web Application Server

A.2.56 CORS_FA_DOMAIN - URI for variable FA_DOMAIN

Parameter	CORS_FA_DOMAIN
Description	URI for substitution variable FA_DOMAIN for setting secure redirect for Cross Origin Resource Sharing.
Ordinality	Optional. May be needed only if CORS for embedded UI is true.
Valid Values	URI
Tier	Web Application Server

Depending on the URL that is used to invoke **OUAF** application, **FW_DOMAIN** and **AML_DOMAIN** substitution variables may be needed to be set.

Example:

http://[splhost:port]/spl/cis.jsp?app=[appname]&host=@FA_DOMAIN@&path=/[somepath|http://

[splhost:port]/spl/cis.jsp?app=%5bappname%5d&host=@FA_DOMAIN@&path=/%5bsomepath]

A.2.57 CORS_HOST – Source for Cross Origin Resource Sharing

Parameter	CORS_HOST
Description	Specifies the Cross Origin Resource Sharing source host if ENABLE_CORS is set to true.
Ordinality	Optional
Valid Values	Host Address/URL
Tier	Web Application Server

Note: The URI must be listed in whitelist.xml file and the whitelist.xml's file location should be specified against com.oracle.couaf.whitelist.file property in spl.properties.

A.2.58 CORS_SCHEME – Scheme to be used for Cross Origin Resource Sharing

Parameter	CORS_SCHEME
Description	Specifies the Cross Origin Resource Sharing communication scheme to be used if ENABLE_CORS is set to true .
Ordinality	Optional
Valid Values	[http https]
Tier	Web Application Server

A.2.59 CSRF_PROTECTION – Cross-Site Request Forgery Protection

Parameter	CSRF_PROTECTION
Description	Specifies if Cross-Site Request Forgery protection is enabled or disabled.
Ordinality	Mandatory
Valid Values	[true false]
Tier	Web Application Server, Business Application Server, Background Processing

A.2.60 CUSTOM_SQL_SECURITY – Enable Custom SQL Security

Parameter	CUSTOM_SQL_SECURITY
Description	Specifies if custom SQL security is enabled or disabled.
Ordinality	Mandatory
Valid Values	[true false]
Tier	Web Application Server, Business Application Server, Background Processing

A.2.61 DBCONNECTION - JDBC Connection String

Parameter	DBCONNECTION
Description	Generated Database JDBC string. This is generated from the DBSERVER / DBPORT / DBNAME or
	DB_OVERRIDE_CONNECTION. As this is generated, it should not be altered.
	Customers using Native mode installation can replace this connection with JDBC Data Sources, if desired.
Ordinality	Mandatory
Valid Values	Generated URL
Tier	Business Application Server, Background Processing, Database

A.2.62 DBDRIVER - Database Driver

Parameter	DBDRIVER
Description	Database Driver to use.
	Automatically generated by installation.
	This should not be altered.
Ordinality	Mandatory
Valid Values	Generated URL
Tier	Business Application Server, Background Processing, Database

A.2.63 DBNAME - Database Name

Parameter	DBNAME
Description	Oracle Database Instance Name. Customers using Native mode installation can ignore this value if using JDBC Data Sources.
Ordinality	Mandatory
Valid Values	Valid Database instance name
Tier	Business Application Server, Background Processing, Database

A.2.64 DBPASS - Online Database User Password

Parameter	DBPASS
Description	Encrypted database user password for the online component of the product. Password for <u>DBUSER</u> .
Ordinality	Mandatory
Valid Values	Encrypted Password
Tier	Business Application Server, Background Processing, Database

A.2.65 DBPASS_GEOCODE_WLS - GEOCODE Database Password

Parameter	DBPASS_GEOCODE_WLS
Description	Encrypted database user password for the GEOCODE integration. Password for DBUSER GEOCODE .
Ordinality	Mandatory
Valid Values	Encrypted Password
Tier	Business Application Server, Database

A.2.66 DBPASS_MDS - MDS Database Password

Parameter	DBPASS_MDS
Description	Encrypted database user password for the SOA Suite Meta Data Service (MDS) integration. Password for DBUSER_MDS .
	This password was specified as part of the <u>SOA Suite database</u> <u>installation process</u> for the <u>prefix_MDS</u> user.
	This is only valid for products that include Oracle SOA Suite. This is used for deployment of content to Oracle SOA Suite for integration.
Ordinality	Mandatory
Valid Values	Encrypted Password
Tier	Business Application Server, Background Processing, Database

A.2.67 DBPASS_ORASDPM - DPM Database Password

Parameter	DBPASS_ORASDPM
Description	Encrypted database user password for the SOA Suite User Message Services (DPM) integration. Password for DBUSER ORASDPM .
	This password was specified as part of the <u>SOA Suite database</u> installation process for the prefix_ORASDPM user.
	This is only valid for products that include Oracle SOA Suite. This is used for deployment of content to Oracle SOA Suite for integration.
Ordinality	Mandatory
Valid Values	Encrypted Password
Tier	Business Application Server, Background Processing, Database

A.2.68 DBPASS_OSB - OSB Database Password

Parameter	DBPASS_OSB
Description	Encrypted database user password for the Oracle Service Bus (OSB) integration. Password for DBUSER_OSB .
	This password was specified as part of the <u>Oracle Service Bus</u> <u>installation</u> for the OSB database user.
	This is only valid for products that include Oracle Service Bus. This is used for deployment of content to Oracle Service Bus for integration. This is not used for the Oracle Service Bus Adapters for Oracle Utilities.
Ordinality	Mandatory
Valid Values	Encrypted Password
Tier	Business Application Server, Background Processing, Database

A.2.69 DBPASS_SOAINFRA - SOA Database Password

Parameter	DBPASS_SOAINFRA
Description	Encrypted database user password for the SOA Suite integration. Password for DBUSER SOAINFRA .
	This password was specified as part of the <u>SOA Suite database</u> <u>installation process</u> for the <u>prefix_SOAINFRA</u> user.
	This is only valid for products that include Oracle SOA Suite. This is used for deployment of content to Oracle SOA Suite for integration.
Ordinality	Mandatory
Valid Values	Encrypted Password
Tier	Business Application Server, Background Processing, Database

A.2.70 DBPORT - Database Listener Port

Parameter	DBPORT
Description	Oracle Listener port for connection to the database. Customers using Native mode installation can ignore this value if using JDBC Data Sources.
Ordinality	Mandatory
Valid Values	Valid Port Number
Tier	Business Application Server, Background Processing, Database

A.2.71 DBSERVER - Database Server

Parameter	DBSERVER
Description	Oracle Database Host Name. Customers using Native mode installation can ignore this value if using JDBC Data Sources.
Ordinality	Mandatory
Valid Values	Valid Host Name
Tier	Business Application Server, Background Processing, Database

A.2.72 DBURL_GEOCODE - GEOCODE JDBC URL

Parameter	DBURL_GEOCODE
Description	Oracle Database JDBC URL used for Geocoding.
	This is set for products using Oracle Spatial.
Ordinality	Mandatory
Valid Values	Valid JDBC URL
Tier	Business Application Server, Background Processing, Database

A.2.73 DBURL_OSB - OSB JDBC URL

Parameter	DBURL_OSB
Description	Oracle Database JDBC URL for Oracle Service Bus.
	This is used for deploying content to Oracle Service Bus.
Ordinality	Mandatory
Valid Values	Valid JDBC URL
Tier	Business Application Server, Background Processing, Database

A.2.74 DBURL_SOA - SOA Suite JDBC URL

Parameter	DBURL_SOA
Description	Oracle Database JDBC URL for Oracle SOA Suite. This is used for deploying content to Oracle SOA Suite.
Ordinality	Mandatory
Valid Values	Valid JDBC URL
Tier	Business Application Server, Background Processing, Database

A.2.75 DBUSER - Online Database User

Parameter	DBUSER
Description	Database User, with Read/Write permissions used for pooled connections for online transactions.
Ordinality	Mandatory
Valid Values	Valid Database User used in installation
Tier	Business Application Server, Background Processing, Database

A.2.76 DBUSER_GEOCODE - GEOCODE Database User

Parameter	DBUSER_GEOCODE
Description	Database User, with connection to Geocode Database.
Ordinality	Mandatory
Valid Values	Valid Database User on target database
Tier	Business Application Server, Background Processing, Database

A.2.77 DBUSER_MDS - SOA MDS Database User

Parameter	DBPASS_MDS
Description	Database user password for the SOA Suite Meta Data Services (MDS) integration.
	This User ID was specified as part of the <u>SOA Suite database installation</u> <u>process</u> for the <u>prefix_MDS</u> user.
	This is only valid for products that include Oracle SOA Suite. This is used for deployment of content to Oracle SOA Suite for integration.
Ordinality	Mandatory
Valid Values	Valid Database User (prefix_MDS) on target database
Tier	Business Application Server, Background Processing, Database

A.2.78 DBUSER_ORASDPM - DPM Database User

Parameter	DBPASS_ORASDPM
Description	Database user password for the SOA Suite User Messaging Services (DPM) integration.
	This User ID was specified as part of the <u>SOA Suite database installation</u> <u>process</u> for the <u>prefix_ORASDPM</u> user.
	This is only valid for products that include Oracle SOA Suite. This is used for deployment of content to Oracle SOA Suite for integration.
Ordinality	Mandatory
Valid Values	Valid Database User (prefix_ORASDPM) on target database
Tier	Business Application Server, Background Processing, Database

A.2.79 DBUSER_OSB - OSB Database User

Parameter	DBPASS_OSB
Description	Database user password for the Oracle Service Bus integration. This User ID was specified as part of the Oracle Service Bus database installation process. This is only valid for products that include Oracle Service Bus. This is used for deployment of content to Oracle Service Bus for integration.
Ordinality	Mandatory
Valid Values	Valid Database User on target database
Tier	Business Application Server, Background Processing, Database

A.2.80 DBUSER_SOAINFRA - SOA Database User

Parameter	DBPASS_SOAINFRA
Description	Database user password for the SOA Suite integration.
	This User ID was specified as part of the <u>SOA Suite database installation</u> <u>process</u> for the <u>prefix_SOAINFRA</u> user.
	This is only valid for products that include Oracle SOA Suite. This is used for deployment of content to Oracle SOA Suite for integration.
Ordinality	Mandatory
Valid Values	Valid Database User (prefix_SOAINFRA) on target database
Tier	Business Application Server, Background Processing, Database

A.2.81 DB_OVERRIDE_CONNECTION - Custom JDBC URL

Parameter	DB_OVERRIDE_CONNECTION
Description	Database JDBC Override string. For customers using Oracle 12c, use a string in the following format to support Pluggable Databases: jdbc:oracle:thin:@// <host>:<port>/<pdbname></pdbname></port></host>
	Customers using Native mode installation can replace this connection with JDBC Data Sources, if desired.
Ordinality	Mandatory
Valid Values	Valid JDBC URL.
Tier	Business Application Server, Background Processing, Database

A.2.82 DESC - Environment Description

Parameter	DESC
Description	Environment Description. Used for documentation purposes only.
Ordinality	Optional
Valid Values	String Value
Tier	Not Applicable

A.2.83 DIALECT - Hibernate Dialect

Parameter	DIALECT
Description	Hibernate Dialect This is the database dialect used by Hibernate to process database requests. This is automatically generated by the installer and should not be altered.
Ordinality	Mandatory
Valid Values	Valid Hibernate Dialects
Tier	Business Application Server, Background Processing, Database

A.2.84 DIRSEP - Directory Separator

Parameter	DIRSEP
Description	Directory Separator This is an internal setting that sets the directory separator applicable for the platform. It is used by various scripts to set the paths correctly for the operating system. It is automatically generated at installation time and should not be altered.
Ordinality	Mandatory
Valid Values	Directory Separator character
Tier	Web Application Server, Business Application Server, Inbound Web Services, Background Processing

A.2.85 DOC1BILLSCRIPT - Name of External Print Script

Parameter	DOC1BILLSCRIPT
Description	This setting sets the name of the external printing script used for printing extracts using Oracle Documaker. It is generated by individual products that support this feature.
Ordinality	Mandatory
Valid Values	Name of supplied script
Tier	Web Application Server, Business Application Server, Inbound Web Services, Background Processing

A.2.86 DOC1SCRIPT - Name of Generic Print Script

Parameter	DOC1SCRIPT DOC1SCRIPT
Description	This setting sets the name of the generic printing script used for extracts using <u>Oracle Documaker</u> . It is generated by individual products that support this feature.
Ordinality	Mandatory
Valid Values	Name of supplied script
Tier	Web Application Server, Business Application Server, Inbound Web Services, Background Processing

A.2.87 ENABLE_CORS – Enable Cross Origin Resource Sharing

Parameter	ENABLE_CORS
Description	This specifies if OUAF is Cross Origin Resource Sharing enabled for embedded UI.
Ordinality	Optional
Valid Values	[true false]
Tier	Web Application Server

A.2.88 ENABLE_JMS_GLOBAL_FLUSH – Enable Flushing of JMS

Parameter	ENABLE_JMS_GLOBAL_FLUSH
Description	This specifies if the global JMS flusing is enabled.
Ordinality	Mandatory
Valid Values	[true false]
Tier	Web Application Server, Business Application Server, Inbound Web Services, Background Processing

A.2.89 ENCODING - Whether Encryption Is Enabled

Parameter	ENCODING
Description	Enables or Disables encryption across the product. By default, encryption is enabled (true) and is recommended to be enabled for all environments.
Ordinality	Mandatory
Valid Values	[true false]
Tier	Web Application Server, Business Application Server, Inbound Web Services, Background Processing

A.2.90 ENVIRONMENT_ID - Environment Identifier

Parameter	ENVIRONMENT_ID
Description	Unique identifier for each environment or copy of the product. This is specified at installation time to link disparate installations into a single environment for management purposes.
	This setting is used by the Oracle Application Management Pack for Oracle Utilities within Oracle Enterprise Manager to link disparate targets across a number of hosts into a single Oracle Utilities Environment target.
Ordinality	Mandatory
Valid Values	Autogenerated
Tier	Web Application Server, Business Application Server, Inbound Web Services, Background Processing

A.2.91 FORCE_HTTP - Enforce HTTP Protocol

Parameter	FORCE_HTTP
Description	Specifies if http protocol needs to be enforced.
Ordinality	Mandatory
Valid Values	[true false]
Tier	Web Application Server, Business Application Server, Inbound Web Services, Background Processing

A.2.92 FW_VERSION - Oracle Utilities Application Framework Version

Parameter	FWVERSION
Description	Oracle Utilities Application Version This is an internal setting that is generated upon installation of the
	product, service pack installation or upgrade installation.
	This setting is automatically generated at installation time and should not be altered.
Ordinality	Mandatory
Valid Values	Valid Oracle Utilities Application Framework version
Tier	Not Applicable

A.2.93 FW_VERSION_NUM - Oracle Utilities Application Framework Version Identifier

Parameter	FW_VERSION_NUM
Description	Oracle Utilities Application Version This is an internal setting that is generated upon installation of the product, service pack installation or upgrade installation. It is automatically generated at installation time and should not be altered.
Ordinality	Mandatory
Valid Values	Valid Oracle Utilities Application Framework version
Tier	Not Applicable

A.2.94 GIS - GIS Support

Parameter	GIS
Description	Enables or Disables GIS support within the product. This setting is only used by products that use GIS integration. Setting this value to true enabled all other GIS settings.
Ordinality	Mandatory
Valid Values	[true false]
Tier	Web Application Server, Business Application Server, Background Processing

A.2.95 GIS_URL - GIS Service URL

Parameter	GIS_URL
Description	Specifies the GIS JNDI URL used for connections. This setting is only used by products that use GIS integration. This setting is only used if GIS is set to true.
Ordinality	Mandatory
Valid Values	Valid JNDI URL
Tier	Web Application Server, Business Application Server, Background Processing

A.2.96 GIS_WLSYSPASS - GIS WebLogic System Password

Parameter	GIS_WLSYSPASS
Description	Encrypted JNDI Password for GIS integration. This setting is only used by products that use GIS integration. This setting is only used if GIS is set to true.
Ordinality	Mandatory
Valid Values	Valid Encrypted Password
Tier	Web Application Server, Business Application Server, Background Processing

A.2.97 GIS_WLSYSUSER - GIS WebLogic System User Id

Parameter	GIS_WLSYSUSER
Description	Encrypted JNDI User for GIS integration. This setting is only used by products that use GIS integration. This setting is only used if GIS is set to true.
Ordinality	Mandatory
Valid Values	Valid Encrypted User
Tier	Web Application Server, Business Application Server, Background Processing

A.2.98 GLOBAL_JVMARGS - Additional JVM Arguments

Parameter	GLOBAL_JVMARGS
Description	Specific additional JVM options for the online component of the product for Oracle JVM (to enable advanced features)
Ordinality	Mandatory
Valid Values	This is generated
Tier	Web Application Server, Business Application Server

A.2.99 HEADEND_CD_CB - Headend System URI for SOA Configuration Plan (CD_CB)

Parameter	HEADEND_CD_CB
Description	URI as configure in SOA Suite Configuration Plan for Headend System for the CD_DB interface (Echelon). This setting is only available to products interfacing to headend systems.
	This setting is only available to products interfacing to headend systems using SOA Suite.
Ordinality	Mandatory
Valid Values	Valid SOA Suite URI for CD_DB interface.
Tier	Business Application Server

A.2.100 HEADEND_MR_CB - Headend System URI for SOA Configuration Plan (MR_CB)

Parameter	HEADEND_MR_CB
Description	URI as configure in SOA Suite Configuration Plan for Headend System for the MR_DB interface (Echelon).
	This setting is only available to products interfacing to head end systems using SOA Suite.
Ordinality	Mandatory
Valid Values	Valid SOA Suite URI for MR_DB interface.
Tier	Business Application Server

A.2.101 HIBERNATE_JAR_DIR - Location of Hibernate JAR Files

Parameter	HIBERNATE_JAR_DIR
Description	Location of the Hibernate JAR files. This setting is used by the installer to copy the relevant files to the desired locations for deployment.
	This setting is only used at installation time but is registered for potential post release use.
Ordinality	Mandatory
Valid Values	Valid location of Hibernate JAR Files as outlined in the <i>Oracle Revenue Management and Billing Installation Guide</i> .
Tier	Business Application Server, Inbound Web Services, Background Processing

A.2.102 HIGHVALUE - Language Specific Highvalues

Parameter	HIGHVALUE
Description	High value used for SQL queries.
	This is auto generated at installation time.
Ordinality	Mandatory
Valid Values	This value is automatically generated and should not be altered.
Tier	Web Application Server, Business Application Server, Inbound Web Services, Background Processing

A.2.103 HSTS_MAX_AGE – Maximum Age of Strict Transport Security

Parameter	HSTS_MAX_AGE
Description	Maximum age of strict transport security.
Ordinality	Optional. Default value is 31536000.
Valid Values	Value in seconds.
Tier	Web Application Server

A.2.104 HSTS_PRELOAD – Strict Transport Security Preload

Parameter	HSTS_PRELOAD
Description	Preload of strict transport security.
Ordinality	Optional
Valid Values	[true false]. Default value is false.
Tier	Web Application Server

A.2.105 HSTS_SUBDOMAINS – Subdomains Included in Strict Transport Security

Parameter	HSTS_SUBDOMAINS
Description	Subdomains that are included in strict transport security.
Ordinality	Optional
Valid Values	[true false]. Default value is true.
Tier	Web Application Server

A.2.106 IWS_JDBC_NAME - JNDI Name for the IWS Connection Pools

Parameter	IWS_JDBC_NAME
Description	This is the JDBC Data Source connection name used for inbound web services. The JDBC Data Source should be created prior to setting this value using the Configuring JDBC Data Sources instructions.
Ordinality	Optional
Valid Values	Valid fully qualified JNDI name for JDBC Data Source.
Tier	Inbound Web Services

A.2.107 IWSWAR - Name of Inbound Web Services WAR

Parameter	IWSWAR
Description	Default Name for inbound web services application Name.
Ordinality	Mandatory
Valid Values	Valid Server Application Names
Tier	Inbound Web Services

A.2.108 JAVAENCODING - Java Language Encoding

Parameter	JAVAENCODING
Description	Encoding string for Java to support appropriate character sets.
Ordinality	Mandatory
Valid Values	Valid <u>Java Encoding</u> (java.lang). Default: UTF8
Tier	Web Application Server, Business Application Server, Inbound Web Services, Background Processing

A.2.109 JAVA_HOME - Location of Java SDK

Parameter	JAVA_HOME
Description	Location of JDK for use with product
Ordinality	Mandatory
Valid Values	Valid JAVA_HOME location
Tier	Web Application Server, Business Application Server, Inbound Web Services, Background Processing

A.2.110 JAVA_VENDOR - Java Vendor

Parameter	JAVA_VENDOR
Description	JVM Vendor
Ordinality	Mandatory
Valid Values	Generated and used in other utilities
Tier	Web Application Server, Business Application Server, Inbound Web Services, Background Processing

A.2.111 JAVA_VERSION - JVM Version String

Parameter	JAVA_VERSION
Description	Fully qualified JVM version string
Ordinality	Mandatory
Valid Values	Generated and used in other utilities
Tier	Web Application Server, Business Application Server, Inbound Web Services, Background Processing

A.2.112 JAVA_VERSION_MAIN - Abbreviated JVM Version

Parameter	JAVA_VERSION_MAIN
Description	Abbreviated JVM version string
Ordinality	Mandatory
Valid Values	Generated and used in other utilities
Tier	Web Application Server, Business Application Server, Inbound Web Services, Background Processing

A.2.113 JDBC_NAME - JNDI Name for the Online JDBC Data Source

Parameter	JDBC_NAME
Description	This is the JDBC Data Source connection name used for Online channel. The JDBC Data Source should be created prior to setting this value using the Configuring JDBC Data Sources instructions.
Ordinality	Optional
Valid Values	Valid fully qualified JNDI name for JDBC Data Source.
Tier	Web Application Server

A.2.114 JDBC_TIMEOUT - JDBC Read Timeout

Parameter	JDBC_TIMEOUT
Description	Disable Cross Site Request Forgery token validation for REST Services. The JDBC Data Source should be created prior to setting this value using the Configuring JDBC Data Sources instructions.
Ordinality	Optional
Valid Values	The value should be in milliseconds, the default is 600000 (10 minutes).
Tier	Web Application Server

A.2.115 JNDI_GEOCODE - Geocode Data Source JNDI

Parameter	JNDI_GEOCODE
Description	JNDI name for the Geocode Data Source. This parameter is used for the Geocode interface.
	This parameter is only valid for products that use the Geocode interface.
Ordinality	Mandatory
Valid Values	Valid JNDI for Geocode Data Source
Tier	Business Application Server, Background Processing, MOB

A.2.116 JMX_HTTPSSL_FLAG - SSL flag for JMX

Parameter	JMX_HTTPSSL_FLAG
Description	SSL flag setting for JMX. This needs to be set to true for SSL enabled.
Ordinality	Optional
Valid Values	[true false]
Tier	Business Application Server

A.2.117 JMX_HTTPSSL_KEYPAIR_PASSPHRASE - Keypair Passphrase for REST JMX

Parameter	JMX_HTTPSSL_KEYPAIR_PASSPHRASE
Description	Keypair passphrase for REST JMX.
Ordinality	Optional
Valid Values	Passphrase in plain text
Tier	Business Application Server

A.2.118 JMX_HTTPSSL_KEYSTORE_FILE - Keystore file path for REST JMX

Parameter	JMX_HTTPSSL_KEYSTORE_FILE
Description	Keystore file path for REST JMX.
Ordinality	Optional
Valid Values	File path to keystore file Tier
Tier	Business Application Server

A.2.119 JMX_HTTPSSL_KEYSTORE_TYPE - Keystore type for REST JMX

Parameter	JMX_HTTPSSL_KEYSTORE_TYPE
Description	Keystore type for REST JMX
Ordinality	Optional
Valid Values	Type of keystore
Tier	Business Application Server

A.2.120 JMX_HTTPSSL_KEYSTORE_PASSPHRASE - Keystore Passphrase for REST JMX

Parameter	JMX_HTTPSSL_KEYSTORE_PASSPHRASE
Description	Keystore passphrase for REST JMX.
Ordinality	Optional
Valid Values	Passphrase to access keystore
Tier	Business Application Server

A.2.121 JMX_HTTPSSL_TRUSTSTORE_FILE - Truststore file path for REST JMX

Parameter	JMX_HTTPSSL_TRUSTSTORE_FILE
Description	Truststore file path for REST JMX.
Ordinality	Optional
Valid Values	File path of the trust store
Tier	Business Application Server

A.2.122 JMX_HTTPSSL_TRUSTSTORE_PASSPHRASE - Truststore Passphrase for REST JMX

Parameter	JMX_HTTPSSL_TRUSTSTORE_PASSPHRASE
Description	Passphrase to access trust store for REST JMX.
Ordinality	Optional
Valid Values	Plain text passphrase
Tier	Business Application Server

A.2.123 JMX_HTTPSSL_TRUSTSTORE_TYPE - Truststore Type for REST JMX

Parameter	JMX_HTTPSSL_TRUSTSTORE_TYPE
Description	Truststore type for REST JMX.
Ordinality	Optional
Valid Values	Type of trust store
Tier	Business Application Server

A.2.124 JMX_REST_CONTEXT - JMX REST Server Context

Parameter	JMX_REST_CONTEXT
Description	Server context for JMX REST server.
Ordinality	Optional
Valid Values	Default value: amp
Tier	Business Application Server

A.2.125 JMX_REST_PORT_BATCH - Batch Server JMX Port Number for REST Server

Parameter	JMX_REST_PORT_BATCH
Description	Port number of batch server JMX, for REST service.
Ordinality	Optional
Valid Values	Port number
Tier	Business Application Server

A.2.126 JMX_REST_PORT_SERVICE - Business Server JMX Port Number for REST Server

Parameter	JMX_REST_PORT_SERVICE
Description	Port number of business server JMX, for REST service.
Ordinality	Optional
Valid Values	Port number
Tier	Business Application Server

A.2.127 JMX_REST_PORT_WEB - Web Server JMX Port Number for REST Server

Parameter	JMX_REST_PORT_WEB
Description	Port number of business server JMX, for REST service.
Ordinality	Optional
Valid Values	Port number
Tier	Business Application Server

A.2.128 JMX_REST_SERVICE_FLAG - Enable/Disable REST Service for JMX

Parameter	JMX_REST_SERVICE_FLAG
Description	Setting this to true enables REST service for JMX.
Ordinality	Mandatory
Valid Values	[true false]
Tier	Business Application Server

A.2.129 JMX_REST_SERVICE_HOST - Hostname to Run the REST Server

Parameter	JMX_REST_SERVICE_HOST
Description	Hostname to run the REST server for JMX.
Ordinality	Optional
Valid Values	Hostname URI Default value is localhost
Tier	Business Application Server

A.2.130 JNDI_OSB - OSB Data Source JNDI

Parameter	JNDI_OSB
Description	JNDI name for the Oracle Service Bus Data Source. This parameter is used for the Oracle Service Bus interface. This parameter is only valid for products that ship integration that requires Oracle Service Bus.
Ordinality	Mandatory
Valid Values	Valid JNDI for Oracle Service Bus Data Source
Tier	Business Application Server, Background Processing

A.2.131 KS_IMPORT_KEYSTORE_FOLDER – Keystore Import Folder

Parameter	KS_IMPORT_KEYSTORE_FOLDER
Description	Keystore import folder. Populate this option if you want to import the keystore files from an external location. The import will happen only in case of initial install or initialSetup.sh cmd -s.
Ordinality	Mandatory
Valid Values	Valid location for <u>keystore folder</u> .
Tier	Web Application Server, Business Application Server, Inbound Web Services, Background Processing

A.2.132 LD_LIBRARY_PATH - Library Path for Windows/Linux/Solaris

Parameter	LD_LIBRARY_PATH
Description	Generated Library Path for Windows and Linux
Ordinality	Mandatory
Valid Values	This value is generated by the product installer.
Tier	Web Application Server, Business Application Server, Inbound Web Services, Background Processing

A.2.133 MODULES - Names of Modules Installed (Deprecated)

Parameter	MODULES
Description	Generated list of modules. This is generated by the product installer. This parameter is provided for backward compatibility as modules installed are now auto generated from installation records.
Ordinality	Optional
Valid Values	Calculated inside processTemplate.plx
Tier	Web Application Server, Business Application Server, Inbound Web Services, Background Processing

A.2.134 MALWARE_SCAN_HOST

Parameter	MALWARE_SCAN_HOST
Description	URI for malware scanning of attachments.
Ordinality	Optional
Valid Values	URI for the malware scanning.
Tier	Business Application Server

A.2.135 MALWARE_SCAN_PORT

Parameter	MALWARE_SCAN_PORT
Description	Port for malware scanning of attachments.
Ordinality	Optional
Valid Values	Port number.
Tier	Business Application Server

A.2.136 MALWARE_SCAN_TIMEOUT

Parameter	MALWARE_SCAN_TIMEOUT
Description	Timeout for custom malware scanning of attachments i.e., the maximum wait time for completing the scan of an attachment using the malware scanner.
Ordinality	Optional
Valid Values	Time in seconds.
Tier	Business Application Server

A.2.137 NLS_LANG - NLS Language Setting

Parameter	NLS_LANG
Description	Globalization Language setting for the database.
Ordinality	Mandatory
Valid Values	Valid NLS_LANG. Default: AMERICA_AMERICAN. AL32UTF8
Tier	Business Application Server, Inbound Web Services, Background Processing, Database

A.2.138 ONLINE_DISPLAY_HOME - Location of Print Rendering Software

Parameter	ONLINE_DISPLAY_HOME
Description	Location of Print Rendering Software such as Oracle Documaker or Group 1 Doc 1.
Ordinality	Optional
Valid Values	Valid product location of the print rendering software
Tier	Business Application Server, Background Processing

A.2.139 ONS_JAR_DIR - Location of Oracle Notification Service Libraries

Parameter	ONS_JAR_DIR
Description	Location of Oracle Notification Services Libraries used for RAC Fast Connection Failover support.
Ordinality	Optional
Valid Values	Valid location of ons.jar file. Usually \$ORACLE_HOME/opmn/lib
Tier	Business Application Server, Background Processing, Database

A.2.140 ONSCONFIG - ONS Configuration

Parameter	ONSCONFIG
Description	ONS configuration string used for RAC Fast Connection Failover support. For example: racnode1.my.com:4200,racnode2.my.com:4200
Ordinality	Optional
Valid Values	ONS configuration string without nodes= prefix.
Tier	Business Application Server, Background Processing, Database

A.2.141 OPSYS - Operating System

Parameter	OPSYS
Description	Internal variable used for platform specific configurations to be implemented.
Ordinality	Mandatory
Valid Values	Generated Operating System String
Tier	Web Application Server, Business Application Server, Inbound Web Services, Background Processing

A.2.142 ORACLE_CLIENT_HOME - Oracle Client Home

Parameter	ORACLE_CLIENT_HOME
Description	Location of Oracle Client Software or Oracle Home. This is used for ONS and/or the Perl runtime.
Ordinality	Mandatory
Valid Values	Location of Oracle Client Installation. If the Oracle Database software is installed on the same machine, then this can be ORACLE_HOME .
Tier	Web Application Server, Business Application Server, Inbound Web Services, Background Processing

A.2.143 ORACLE_GUIDED_LEARNING_ID - Oracle Guided Learning ID

Parameter	ORACLE_GUIDED_LEARNING_ID
Description	ID of Oracle Guided Learning
Ordinality	Mandatory
Valid Values	Valid ID of Oracle Guided Learning.
Tier	Web Application Server

A.2.144 OSB_HOME - Oracle Service Bus Home

Parameter	OSB_HOME
Description	Location of Oracle Service Bus. This is used to deploy Oracle Service Bus content. This setting only applies to products with prebuilt Oracle Service Bus content.
	This is not used for Oracle Service Bus Adapters.
Ordinality	Optional
Valid Values	Location of Oracle Service Bus installation.
Tier	Business Application Server

A.2.145 OSB_HOST - Oracle Service Bus Host Name

Parameter	OSB_HOST
Description	Host Name for Oracle Service Bus. This is used to deploy Oracle Service Bus content. This setting only applies to products with prebuilt Oracle Service Bus content. This is not used for Oracle Service Bus Adapters.
Ordinality	Optional
Valid Values	Host Name for Oracle Service Bus.
Tier	Business Application Server

A.2.146 OSB_LOG_DIR - Default Location For Oracle Service Bus Logs

Parameter	OSB_LOG_DIR
Description	Logging Directory Oracle Service Bus. This is used to deploy Oracle Service Bus content. This setting only applies to products with prebuilt Oracle Service Bus content. This is not used for Oracle Service Bus Adapters.
Ordinality	Optional
Valid Values	Logging directory for Oracle Service Bus content deployment.
Tier	Business Application Server

A.2.147 OSB_PASS_WLS - Password for Oracle Service Bus User

Parameter	OSB_PASS_WLS
Description	Encrypted password for OSB deployment user (OSB_USER). This is used to deploy Oracle Service Bus content. This setting only applies to products with prebuilt Oracle Service Bus content. This is not used for Oracle Service Bus Adapters.
Ordinality	Optional
Valid Values	Generated Password.
Tier	Business Application Server

A.2.148 OSB_PORT_NUMBER - Oracle Service Bus Port Number

Parameter	OSB_PORT_NUMBER
Description	Port number allocated to Oracle Service Bus. This is used to deploy Oracle Service Bus content. This setting only applies to products with prebuilt Oracle Service Bus content. This is not used for Oracle Service Bus Adapters.
Ordinality	Optional
Valid Values	Valid Administration port to use for deployment of content.
Tier	Business Application Server

A.2.149 OSB_USER - User Name for Oracle Service Bus

Parameter	OSB_USER
Description	Administration user used for OSB deployment user. This is used to deploy Oracle Service Bus content. This setting only applies to products with prebuilt Oracle Service Bus content. This is not used for Oracle Service Bus Adapters.
Ordinality	Optional
Valid Values	Valid Administration user to use for deployment of content.
Tier	Business Application Server

A.2.150 OUAF_DBMS_SCHEDULER_USER – DB User of DBMS Scheduler

Parameter	OUAF_DBMS_SCHEDULER_USER
Description	Database user for DBMS scheduler.
Ordinality	Mandatory
Valid Values	Database User Name. For example, SCHADM
Tier	Background Processing

A.2.151 OWSM_PROTECTION_FOR_REST_SERVICES – Enable Oracle Web Services Manager Protection for REST

Parameter	OWSM_PROTECTION_FOR_REST_SERVICES
Description	Specifies if Oracle Web Services Manager protection is enabled or disabled for REST services.
Ordinality	Mandatory
Valid Values	[true false]
Tier	Web Application Server, Business Application Server, Inbound Web Services

A.2.152 PERLHOME - Location of PERL

Parameter	PERLHOME
Description	Generated location for Perl runtime. Generated from ORACLE CLIENT HOME – Oracle Client Home.
Ordinality	Mandatory
Valid Values	Generated location for Perl.
Tier	Web Application Server, Business Application Server, Inbound Web Services, Background Processing

A.2.153 SERVER_ROLES - Which Server Roles Are Enabled

Parameter	SERVER_ROLES
Description	The server roles are enabled for this installation
Ordinality	Mandatory
Valid Values	Install generated
Tier	Web Application Server, Inbound Web Services, Background Processing

A.2.154 SERVER_ROLE_BATCH - Whether the Batch Server Is Enabled In This Installation

Parameter	SERVER_ROLE_BATCH
Description	Whether this installation is to be used for batch processing
Ordinality	Mandatory
Valid Values	[true false]
Tier	Background Processing

A.2.155 SERVER_ROLE_INTEGRATION - Whether the IWS Server Is Enabled In This Installation

Parameter	SERVER_ROLE_INTEGRATION
Description	Whether this installation is to be used for integration (IWS)
Ordinality	Mandatory
Valid Values	[true false]
Tier	Inbound Web Services

A.2.156 SERVER_ROLE_ONLINE - Whether the Online Server Is Enabled In This Installation

Parameter	SERVER_ROLE_ONLINE
Description	Whether this installation is to be used for online
Ordinality	Mandatory
Valid Values	[true false]
Tier	Inbound Web Services

A.2.157 SOA_HOME - Location of Oracle SOA Suite

Parameter	SOA_HOME
Description	Location of Oracle SOA Suite software. This is used to deploy Oracle SOA Suite content. This setting only applies to products with prebuilt Oracle SOA Suite content.
Ordinality	Optional
Valid Values	Valid location of Oracle SOA Suite.
Tier	Business Application Server

A.2.158 SOA_HOST - Hostname for Oracle SOA Suite

Parameter	SOA_HOST
Description	Hostname for Oracle SOA Suite software. This is used to deploy Oracle SOA Suite content. This setting only applies to products with prebuilt Oracle SOA Suite content.
Ordinality	Optional
Valid Values	Valid host name for Oracle SOA Suite.
Tier	Business Application Server

A.2.159 SOA_PORT_NUMBER - Port Number for Oracle SOA Suite

Parameter	SOA_PORT_NUMBER
Description	Port Number for Oracle SOA Suite software. This is used to deploy Oracle SOA Suite content. This setting only applies to products with prebuilt Oracle SOA Suite content.
Ordinality	Optional
Valid Values	Valid port number for Oracle SOA Suite.
Tier	Business Application Server

A.2.160 SPLADMIN - Administration Userid

Parameter	SPLADMIN
Description	Administration OS user used to install the software. Used by utilities to assign ownership and for deployment purposes.
Ordinality	Mandatory
Valid Values	Valid Administration Account.
Tier	Web Application Server, Business Application Server, Inbound Web Services, Background Processing

A.2.161 SPLADMINGROUP - Administration Group

Parameter	SPLADMINGROUP
Description	Administration OS group used to install the software. Used by utilities to assign ownership and for deployment purposes.
Ordinality	Mandatory
Valid Values	Valid Administration Group.
Tier	Web Application Server, Business Application Server, Inbound Web Services, Background Processing

A.2.162 SPLApp - Name of Online WAR File

Parameter	SPLApp
Description	Name of online WAR file used for building purposes
Ordinality	Mandatory
Valid Values	Valid WAR file name.
Tier	Web Application Server, Business Application Server

A.2.163 SPLDIR - Home Directory of Product

Parameter	SPLDIR
Description	Home Location of product software. This value must match the corresponding entry in <pre>cistab</pre> - Global Configuration Files.
Ordinality	Mandatory
Valid Values	Valid Location of software. Generated by installer.
Tier	Web Application Server, Business Application Server, Inbound Web Services, Background Processing

A.2.164 SPLDIROUT - Location of Product Output

Parameter	SPLDIROUT
Description	Home Location of product output. This value must match the corresponding entry in cistab - Global Configuration Files.
Ordinality	Mandatory
Valid Values	Valid Location of output. Generated by installer.
Tier	Web Application Server, Business Application Server, Inbound Web Services, Background Processing

A.2.165 SPLENVIRON - Environment Identifier

Parameter	SPLENVIRON
Description	Home Location of product output. This value must match the corresponding entry in <u>cistab</u> .
Ordinality	Mandatory
Valid Values	Valid Location of output. Generated by installer.
Tier	Web Application Server, Business Application Server, Inbound Web Services, Background Processing

A.2.166 SPLOUTPUT - Directory for Product Output

Parameter	SPLOUTPUT
Description	Location of product output.
Ordinality	Mandatory
Valid Values	Valid Location of output. Generated by installer.
Tier	Web Application Server, Business Application Server, Inbound Web Services, Background Processing

A.2.167 SPLSERVICEAPP - Name of Business Application Server Application

Parameter	SPLSERVICEAPP
Description	Default name of application which is deployed on business application Server
Ordinality	Mandatory
Valid Values	Valid Server Application Names
Tier	Business Application Server

A.2.168 SPLWEBAPP – Name of Web Application Server Application

Parameter	SPLWEBAPP
Description	Default name of application which is deployed on web application server
Ordinality	Mandatory for Oracle WebLogic implementations
Valid Values	Valid Server Application Names
Tier	Web Application Server

A.2.169 STRICT_TRANSPORT_SECURITY – Enable Strict Transport Security

Parameter	STRICT_TRANSPORT_SECURITY
Description	Enable or Disable transport layer security.
Ordinality	Mandatory
Valid Values	[true false]
Tier	Web Application Server

A.2.170 STRIP_HTML_COMMENTS - Strip Out Comments In Code

Parameter	STRIP_HTML_COMMENTS
Description	Enable or Disable Stripping comments in generated code. By default, code is commented for ease of extension. If these comments represent a security issue for your site, then they can be stripped out at runtime (true).
Ordinality	Mandatory
Valid Values	[true false]
Tier	Business Application Server

A.2.171 TEMPSTORAGE_SPLITFILESIZE - Split File Size in MB

Parameter	TEMPSTORAGE_SPLITFILESIZE
Description	The size of split files in MB, while transferring a file using file adapter API.
Ordinality	Optional
Valid Values	Valid file size in MB. Default is 50.
Tier	Business Application Server

A.2.172 TOP_VERSION - Product Version

Parameter	TOP_VERSION
Description	Product Version identifier string used by utilities and upgrade scripts.
Ordinality	Mandatory
Valid Values	Generated by installer and should not be altered manually.
Tier	Web Application Server, Business Application Server, Inbound Web Services, Background Processing

A.2.173 TOP_VERSION_NUM - High Level Product Version

Parameter	TOP_VERSION_NUM
Description	Product Version identifier number used by utilities and upgrade scripts.
Ordinality	Mandatory
Valid Values	Generated by installer and should not be altered manually.
Tier	Web Application Server, Business Application Server, Inbound Web Services, Background Processing

A.2.174 TMP_FILE_LOCATION - Temporary File Location

Parameter	TMP_FILE_LOCATION
Description	The location of temporary directory where split files from file adapter API are temporarily stored.
Ordinality	Optional
Valid Values	Directory location
Tier	Business Application Server, Background Processing

A.2.175 WEB_ADMIN_SERVER – Name of the Web Admin Server

Parameter	WEB_ADMIN_SERVER
Description	Name of the web admin server.
Ordinality	Mandatory
Valid Values	Server Name
Tier	Web Application Server, Business Application Server, Inbound Web Services, Background Processing

A.2.176 WEB_APP - Name of WebSphere Server Application

Parameter	WEB_APP
Description	Default Name for Web Application Name.
Ordinality	Mandatory for WebSphere implementations
Valid Values	Valid Server Application Names
Tier	Web Application Server

A.2.177 WEB_APPVIEWER_FORM_LOGIN_ERROR_PAGE – App Viewer Form Login Error Page

Parameter	WEB_APPVIEWER_FORM_LOGIN_ERROR_PAGE
Description	Error Page used for invalid AppViewer Login.
Ordinality	Mandatory
Valid Values	Valid JSP for error pages
Tier	Valid JSP for error pages

A.2.178 WEB_APPVIEWER_FORM_LOGIN_PAGE – App Viewer Form Login Page

Parameter	WEB_APPVIEWER_FORM_LOGIN_PAGE
Description	Login Page used for AppViewer Login.
Ordinality	Mandatory
Valid Values	Valid JSP for login

A.2.179 WEB_APPVIEWER_PRINCIPAL_NAME - Application Viewer Principal Name

Parameter	WEB_APPVIEWER_PRINCIPAL_NAME
Description	Principal Name for AppViewer
Ordinality	Mandatory
Valid Values	Valid Principal Name

A.2.180 WEB_APPVIEWER_ROLE_NAME - Application Viewer Security Role

Parameter	WEB_APPVIEWER_ROLE_NAME
Description	Role Name for AppViewer
Ordinality	Mandatory
Valid Values	Valid Role Name

A.2.181 WEB_CONTEXT_ROOT - Web Context Root

Parameter	WEB_CONTEXT_ROOT
Description	Web Context for product
Ordinality	Mandatory
Valid Values	Valid context. Default: spl
Tier	Web Application Server, Business Application Server, Inbound Web Services

A.2.182 WEB_DEPLOY_JAVADOCS - Deploy JavaDocs

Parameter	WEB_DEPLOY_JAVADOCS
Description	Javadocs are deployed if this is set to true
Ordinality	Mandatory
Valid Values	[true false]
Tier	Web Application Server

A.2.183 WEB_DEPLOY_APPVIEWER - Deploy AppViewer

Parameter	WEB_DEPLOY_APPVIEWER
Description	Whether the AppViewer application is included in the online EAR file. A value of true adds the appViewer to the online EAR file. A value of false does not add the appViewer content to the online EAR file.
	Note: If the appViewer is not deployed the online administration functions that use the appViewer will not display this content.
	It is recommended to set this value as false for non-development environments.
Ordinality	Mandatory
Valid Values	[true false]

A.2.184 WEB_DEPLOY_EAR - Deploy EAR File

Parameter	WEB_DEPLOY_EAR
Description	Whether the EAR file is built and deployed or not for development environments.
	It is recommended to set this value to true for non-development environments.
	This setting replaces components of the WEB_ISDEVELOPMENT variable to allow development platforms to use expanded or EAR mode independently.
Ordinality	Mandatory
Valid Values	[true false]
JEE Web Application Server	Oracle WebLogic Application Server
Tier	Web Application Server

A.2.185 WEB_ENABLE_HEALTHCHECK - Enable System Healthcheck

Parameter	WEB_ENABLE_HEALTHCHECK
Description	Enable the system healthcheck function used by the Oracle Application Management Pack for Oracle Utilities available from Oracle Enterprise Manager.
Ordinality	Mandatory
Valid Values	[true false]
Tier	Web Application Server

A.2.186 WEB_FORM_LOGIN_ERROR_PAGE - Default Form Login Error Page

Parameter	WEB_FORM_LOGIN_ERROR_PAGE
Description	Error Page used for invalid online Login.
Ordinality	Mandatory
Valid Values	Valid JSP for error pages
Tier	Web Application Server

A.2.187 WEB_FORM_LOGIN_PAGE - Default Form Login Page

Parameter	WEB_FORM_LOGIN_PAGE
Description	Login Page used for online Login.
Ordinality	Mandatory
Valid Values	Valid JSP for login
Tier	Web Application Server

Note: If WEB_HELP_FORM_LOGIN_ERROR_PAGE and/or WEB_APPVIEWER_FORM_LOGIN_ERROR_PAGE is not specified, then they default to the value specified in WEB_FORM_LOGIN_ERROR_PAGE.

If WEB_HELP_FORM_LOGIN_PAGE and/or WEB_APPVIEWER_FORM_LOGIN_PAGE is not specified, then they default to the value specified in WEB_FORM_LOGIN_PAGE.

If WEB_APPVIEWER_ROLE_NAME and/or WEB_APPVIEWER_PRINCIPAL_NAME is not specified, they are default to WEB_ROLE_NAME and WEB_PRINCIPAL_NAME, respectively.

A.2.188 WEB_HELP_FORM_LOGIN_ERROR_PAGE - Help Form Login Error Page

Parameter	WEB_HELP_FORM_LOGIN_ERROR_PAGE
Description	Error Page used for invalid Help Login.
Ordinality	Mandatory
Valid Values	Valid JSP for error pages
Tier	Web Application Server

A.2.189 WEB_HELP_FORM_LOGIN_PAGE - Help Form Login Page

Parameter	WEB_HELP_FORM_LOGIN_PAGE
Description	Login Page used for Help Login.
Ordinality	Mandatory
Valid Values	Valid JSP for login
Tier	Web Application Server

A.2.190 WEB_ISDEVELOPMENT - Development Environment

Parameter	WEB_ISDEVELOPMENT
Description	Enable or Disable Development on this product environment. This setting assumes that the Oracle Utilities SDK.
Ordinality	Mandatory
Valid Values	[true false]
Tier	Web Application Server, Business Application Server, Inbound Web Services, Background Processing

A.2.191 WEB_ISJAVADOCS - Install application JAVADOCS

Parameter	WEB_ISJAVADOCS
Description	To install application Javadocs, this needs to be set to true.
Ordinality	Optional
Valid Values	[true false]
Tier	Web Application Server

A.2.192 WEB_IWS_MDB_RUNAS_USER - Default User for MDB to Run as within Product

Parameter	WEB_IWS_MDB_RUNAS_USER
Description	The default product user the MDB uses to run its interface. This value is used if no JMS credentials are provided on the message header. A blank value, the default, for this parameter disables the function and assumes all JMS messages will include their credentials in the head of the message.
Ordinality	Optional
Valid Values	Blank (not enabled) or a valid product authorization User ID (not login id)
Tier	Inbound Web Services

A.2.193 WEB_IWS_SUPER_USERS - Users to Run as in IWS

Parameter	WEB_IWS_SUPER_USERS
Description	Default product user used for authorization for inbound web services. This value is used for internal calls used for inbound web services.
Ordinality	Optional
Valid Values	Blank (not enabled) or a valid product authorization User ID (not login id)
Tier	Inbound Web Services

A.2.194 WEB_JAVADOCS_FORM_LOGIN_ERROR_PAGE - Javadocs Login Error Page

Parameter	WEB_JAVADOCS_FORM_LOGIN_ERROR_PAGE
Description	Login error page configuration for javadocs in the application.
Ordinality	Optional
Valid Values	Relative URI to login error page.
	Default value is: /formLoginError.jsp
Tier	Web Application Server

A.2.195 WEB_JAVADOCS_FORM_LOGIN_PAGE - Javadocs Login Page

Parameter	WEB_JAVADOCS_FORM_LOGIN_PAGE
Description	Login page configuration for javadocs in the application.
Ordinality	Optional
Valid Values	Relative URI to login page.
	Default value is: /loginPage.jsp
Tier	Web Application Server

A.2.196 WEB_JAVADOCS_PRINCIPAL_NAME - Javadocs Principal Name

Parameter	WEB_JAVADOCS_PRINCIPAL_NAME
Description	Principal name for javadocs. Specify the name of a principal that is defined in the security realm.
Ordinality	Optional
Valid Values	Principal name.
	Default value is: cisusers
Tier	Web Application Server

A.2.197 WEB_JAVADOCS_ROLE_NAME - Javadocs Security Role Name

Parameter	WEB_JAVADOCS_ROLE_NAME
Description	Security role for javadocs. Specify the name of the security role.
Ordinality	Optional
Valid Values	Application security role. Default value is: cisusers
Tier	Web Application Server

A.2.198 WEB_JMX_RMI_PORT_PERFORMANCE - JMX Port for Web Application Server Monitoring

Parameter	WEB_JMX_RMI_PORT_PERFORMANCE
Description	Port number for JMX monitoring for Online monitoring.
Ordinality	Mandatory
Valid Values	Valid open port number for monitoring.
Tier	Web Application Server

A.2.199 WEB_L2_CACHE_MODE - Turn Off L2 Cache for Online Submission

Parameter	WEB_L2_CACHE_MODE
Description	Enables (on) or disables (off) Level 2 cache for online submission. Used for development purposes where online submission cache is off.
	Note: Some batch processes require L2 Cache to be disabled. Refer to individual job documentation for details.
Ordinality	Mandatory
Valid Values	[on off]
Tier	Web Application Server, Background Processing

A.2.200 WEB_MAXAGE - Text Cache

Parameter	WEB_MAXAGE
Description	Set the duration (in seconds) to store page structures from the product, in the <u>client cache</u> , on the client browser.
Ordinality	Mandatory
Valid Values	See maxAge – Max Age for pages for valid values
Tier	Web Application Server

A.2.201 WEB_MAXAGEI - Image Cache

Parameter	WEB_MAXAGEI
Description	Set the duration (in seconds) to store images, in the <u>client cache</u> , from the product on the client browser.
Ordinality	Mandatory
Valid Values	See maxAgeI – Max Age for Images for valid values
Tier	Web Application Server

A.2.202 WEB_NODENAME - IBM WebSphere ND Node Name

Parameter	WEB_NODENAME
Description	Node Name for IBM WebSphere ND.
Ordinality	Mandatory
Valid Values	Valid IBM WebSphere ND node name
JEE Web Application Server	IBM WebSphere Application Server Network Deployment
Tier	Web Application Server, Business Application Server, Inbound Web Services, XML Application Integration

A.2.203 WEB_PRELOADALL - Preload All Pages on Startup

Parameter	WEB_PRELOADALL
Description	Enable or Disable preload of pages at startup. This determines the scope of any reload. A value of false (default) only preloads the Main menu only. A value of true preloads all functions on all menus. A value of true will lengthen the startup process.
Ordinality	Mandatory
Valid Values	[true false]
Tier	Web Application Server

A.2.204 WEB_PRINCIPAL_NAME - Default JEE Authorization Principal

Parameter	WEB_PRINCIPAL_NAME
Description	Principal Name for online application.
Ordinality	Mandatory
Valid Values	Valid Principal Name. Default: cisusers
Tier	Web Application Server, Business Application Server, Inbound Web Services

A.2.205 WEB_ROLE_NAME - Default JEE Authorization Role

Parameter	WEB_ROLE_NAME
Description	Role Name for online application
Ordinality	Mandatory
Valid Values	Valid Role Name.
	Default: cisusers
Tier	Web Application Server, Business Application Server, Inbound Web Services

A.2.206 WEB_SERVER_HOME - Location of Web Application Server

Parameter	WEB_SERVER_HOME
Description	Generic location of web application server. This value is then used to set the following value: WL_HOME - Oracle WebLogic installation used for the product
Ordinality	Mandatory
Valid Values	Home location of web application server software
Tier	Web Application Server, Business Application Server, Inbound Web Services

A.2.207 WEB_SERVER_VERSION - Web Server Version

Parameter	WEB_SERVER_VERSION
Description	Full Version of JEE web application server. Used for utilities to ensure correct templates are used.
Ordinality	Mandatory
Valid Values	Generated by installer
Tier	Web Application Server, Business Application Server, Inbound Web Services

A.2.208 WEB_SERVER_VERSION_MAIN

Parameter	WEB_SERVER_VERSION_MAIN
Description	Substring Version of JEE web application server. Used for utilities to ensure correct templates are used
Ordinality	Mandatory
Valid Values	Generated by installer
Tier	Web Application Server, Business Application Server, Inbound Web Services

A.2.209 WEB_SERVER_VERSION_PATCH_FLAG

Parameter	WEB_SERVER_VERSION_PATCH_FLAG
Description	Set to "true" if the WLS PATCH SET UPDATE is greater or equal than 12.2.1.3.220329.
Ordinality	Optional
Valid Values	Calculated value by installer.
Tier	Web Application Server, Business Application Server, Inbound Web Services.

A.2.210 WEB_SVRNAME - IBM WebSphere Server Name

Parameter	WEB_SVRNAME
Description	Server Name for IBM WebSphere/IBM WebSphere ND.
Ordinality	Mandatory
Valid Values	Valid IBM WebSphere/IBM WebSphere ND server name
JEE Web Application Server	IBM WebSphere Application Server Network Deployment
Tier	Web Application Server, Business Application Server, Inbound Web Services, XML Application Integration

A.2.211 WEB_WASPASS - IBM WebSphere JNDI Password

Parameter	WEB_WASPASS
Description	Encrypted password for JNDI user for IBM WebSphere/IBM WebSphere ND. This setting is only applicable to IBM WebSphere/IBM WebSphere ND customers.
Ordinality	Mandatory
Valid Values	Encrypted password for JNDI user.
JEE Web Application Server	IBM WebSphere Application Server Network Deployment
Tier	Web Application Server, Business Application Server, Inbound Web Services, XML Application Integration

A.2.212 WEB_WASUSER - IBM WebSphere JNDI UserID

Parameter	WEB_WASUSER
Description	Administration JNDI user for IBM WebSphere/IBM WebSphere ND. This parameter is used for any JNDI calls to the servers. This setting is only applicable to IBM WebSphere/IBM WebSphere ND customers.
Ordinality	Mandatory
Valid Values	JNDI Administration User.
JEE Web Application Server	IBM WebSphere Application Server Network Deployment
Tier	Web Application Server, Business Application Server, Inbound Web Services, XML Application Integration

A.2.213 WEB_WLAUTHMETHOD - Authentication Method

Parameter	WEB_WLAUTHMETHOD
Description	JEE Authorization Method implemented.
Ordinality	Mandatory
Valid Values	Valid values: • FORM (Default) - Use login forms • BASIC - Use Operating System Login • CLIENT-CERT - Client Certificate
Tier	Web Application Server, Business Application Server, Inbound Web Services

A.2.214 WEB_WLHOST - Web Server Host

Parameter	WEB_WLHOST
Description	Host Name for Oracle WebLogic Install.
Ordinality	Mandatory
Valid Values	Valid Host Name
Tier	Web Application Server, Business Application Server, Inbound Web Services

A.2.215 WEB_WLPAGECHECKSECONDS - Interval for Recompilation of JSP

Parameter	WEB_WLPAGECHECKSECONDS
Description	Interval, in seconds, to force recompilation for server JSP's. This is used for Oracle WebLogic customers only. This setting is designed to be altered for development environments. The default is recommended for all other environments.
Ordinality	Mandatory
Valid Values	Valid Recompile time. Default: 43200
Tier	Web Application Server

A.2.216 WEB_WLPORT - Web Server HTTP Port

Parameter	WEB_WLPORT
Description	Port number for environment for online system.
Ordinality	Optional. Value should not be populated if WEB_WLSSLPORT is populated
Valid Values	Valid open port number. Default: 6500
Tier	Web Application Server

A.2.217 WEB_WLSSLPORT - Oracle WebLogic SSL HTTP Port

Parameter	WEB_WLSSLPORT
Description	SSL Port number for environment for online system.
Ordinality	Optional. Value should not be populated if WEB_WLPORT is populated
Valid Values	Valid open port number.
	Default: 6501
Tier	Web Application Server

A.2.218 WEB_WLSYSPASS - Oracle WebLogic JNDI System Password

Parameter	WEB_WLSSYSPASS
Description	Encrypted Oracle WebLogic JNDI Password used for JNDI lookups.
Ordinality	Mandatory
Valid Values	Valid JNDI Password.
Tier	Web Application Server

A.2.219 WEB_WLSYSUSER - Oracle WebLogic JNDI System Userid

Parameter	WEB_WLSSYSUSER
Description	Oracle WebLogic JNDI User used for JNDI lookups. This is used for Oracle WebLogic customers only.
Ordinality	Mandatory
Valid Values	Valid JNDI User
Tier	Web Application Server

A.2.220 WEB_WLS_SVRNAME - Oracle WebLogic Server Name

Parameter	WEB_WLS_SVRNAME
Description	Oracle WebLogic Server Name
Ordinality	Mandatory
Valid Values	Valid Server Name.
	Default: myserver
JEE Web Application Server	WLS
Tier	Web Application Server

A.2.221 WLS_ADMIN_PORT - Admin Console Port Number

Parameter	WLS_ADMIN_PORT
Description	Oracle WebLogic Administration Port. Only supplied if Administration port differs from application port. Oracle WebLogic Server Name. This is used only for Oracle WebLogic customers and embedded installations.
Ordinality	Mandatory
Valid Values	Valid Port Number. Default: Value of WEB_WLPORT-Web Server HTTP Port.
Tier	Web Application Server

A.2.222 WLS_CLUSTER_NAME - Name of Cluster for Product

Parameter	WLS_CLUSTER_NAME
Description	Oracle WebLogic Cluster Name for clustered environments. This value must be set for customers using the Application Management Pack for Oracle Utilities to link the cluster target with the product.
Ordinality	Optional
Valid Values	Valid Cluster Name.
Tier	Web Application Server

A.2.223 WLS_DIAGNOSTIC_CONTEXT_ENABLED - ECID Support

Parameter	WLS_DIAGNOSTIC_CONTEXT_ENABLED
Description	This enables (true) or disables (false) ECID Support.
Ordinality	Optional
Valid Values	{true false}
Tier	Web Application Server

A.2.224 WLS_DOMAIN_HOME - Oracle WebLogic Domain Home

Parameter	WLS_DOMAIN_HOME
Description	Domain Home directory for installation. Used if installation has multiple domains installed
Ordinality	Mandatory
Valid Values	Valid Domain Home
Tier	Web Application Server

A.2.225 WLTHINT3CLIENT_JAR_DIR - Location of Thin WebLogic T3 Client

Parameter	WLTHINT3CLIENT_JAR_DIR
Description	Location of Oracle WebLogic Thin Client for JMX and other interfaces. Used for integration to Oracle products for monitoring.
Ordinality	Optional
Valid Values	Valid location of wlthint3client.jar
Tier	Web Application Server, Inbound Web Services

A.2.226 WL_HOME - Oracle WebLogic Home

Parameter	WL_HOME
Description	Home directory of Oracle WebLogic. This is used only for Oracle WebLogic customers and embedded installations.
Ordinality	Mandatory
Valid Values	Valid console user.
	Default: system
JEE Web Application Server	WLS
Tier	Web Application Server

A.2.227 XAI_DBPASS - Password for Database User for IWS

Parameter	XAI_DBPASS
Description	Encrypted database user password for the inbound web services component of the product.
Ordinality	Mandatory
Valid Values	Encrypted Password
Tier	Inbound Web Services, Database

A.2.228 XAI_DBUSER - Database User for IWS

Parameter	XAI_DBUSER	
Description	Database user with Read/Write permissions used for pooled connections for inbound web services transactions.	
Ordinality	Mandatory	
Valid Values	Valid Database User used in installation	
Tier	Inbound Web Services, Database	

A.2.229 XQUERIES_TO_CACHE - Size of XQuery Cache

Parameter	XQUERIES_TO_CACHE
Description	Size of XQuery/XPath Cache in number of queries. Increasing the cache size may increase memory requirements for the product. This sets the value of com.oracle.XPath.LRUSize in the spl.properties file
Ordinality	Optional
Valid Values	Defaults from templates (-1 - Unlimited in size)
Tier	Business Application Server, Inbound Web Services, Background Processing

A.2.230 XQUERY_CACHE_FLUSH_TIMEOUT - Cache Life for XQueries

Parameter	XQUERY_CACHE_FLUSH_TIMEOUT
Description	Length of time in seconds that XQuery and XPath queries are cached and set the value of com.oracle.XPath.flushTimeout – Xpath Flush in the spl.properties file.
Ordinality	Optional
Valid Values	Defaults from templates (O - Never flush is the default)
Tier	Business Application Server, Inbound Web Services, Background Processing

A.3 Web.xml

The web deployment descriptor editor lets you specify deployment information for modules created in the Web development environment. The information appears in the web.xml file. The web.xml file for a Web project provides information necessary for deploying a Web application module. It is used in building a WAR/EAR file from a project.

The online and web Services JEE applications for the product are controlled by this configuration file which holds the behavioral configuration for the applications. Refer to http://jcp.org/en/jsr/detail?id=109 for more details of the XML format.

The following sections outline the specific settings for the product.

A.3.1 Filter Mappings - JEE Filters

Note: Filters should not be altered unless instructed by Oracle Support. Refer to the web.xml file for the relevant settings.

The following filters apply to the product:

Filter	Usage
Browser Cache Filter	Browser Client-side caching settings - Used with MaxAge – Max Age for pages
CSS Stylesheet Direction Filter	CSS Filter
Doctype Replace Filter	JDOC Filter
FlushAll Redirect Filter	Cache management utility Filter
GZip Compression Filter	HTTP 1.1 compression filter
Header Security Filter	OWASP processing of HTTP headers using SAMEORIGIN
HTML Comment stripping Filter	Removal of comments from HTTP transmission
Image Browser Cache Filter	Browser Client-side caching settings for image files - Used with MaxAgel – Max Age for Images
Image RTL Filter	Right to Left support Filter
Javascript Comment stripping Filter	Removal of comments from javascript transmission
Minification Filter	Optimization code
Privacy Page Redirect Filter	Privacy page redirect to /cm/privacy.html
Request Context Filter	Generic context Filter
Rest Security Filter	REST security support

Filter	Usage
Security Filter	Generic security filter to delegate security to JEE container
Timezone Database ContentType Filter	Time zone support

A.3.2 disableCompression - Disable Compression

Parameter	disableCompression
Description	Enables or disables compression between the Web Application
	Server and Business Application Server (true or false).
Ordinality	Mandatory
Valid Values	[true false]
Source	Derived from <u>WEB_ISDEVELOPMENT - Development Environment</u> parameter from <u>ENVIRON.INI</u> . It is highly recommended to set to false for all environment exception is development environments using Oracle Utilities SDK.
Applicability	Web Application Server
Example	<pre><context-param> <param-name>disableCompression</param-name> <param-value>false</param-value> </context-param></pre>

A.3.3 maxAgel - Max Age for Images

Parameter	maxAge
Description	Set the duration (in seconds) to store images, in the <u>client cache</u> , from the product on the client browser.
Ordinality	Mandatory
Valid Values	As per <u>JEE Standards</u> Default: 28850
Source	Derived from <u>WEB_MAXAGEI - Image Cache</u> parameter from <u>ENVIRON.INI</u> . It is highly recommended to set to the default unless otherwise recommended.
Applicability	Web Application Server
Example	<filter> <filter-name>Image Browser Cache Filter</filter-name> <filter- class="">com.splwg.base.web.services.BrowserCacheFilter <init-param> <param-name>maxAge</param-name> <param-value>28850</param-value> </init-param> </filter-></filter>

A.3.4 maxAge - Max Age for Pages

Parameter	maxAge
Description	Set the duration (in seconds) to store page structures from the product, in the <u>client cache</u> , on the client browser.
Ordinality	Mandatory
Valid Values	As per <u>JEE Standards</u>
	Default: 28850
Source	Derived from <u>WEB MAXAGE – Text Cache</u> parameter from <u>ENVIRON.INI</u> . It is highly recommended to set to the default unless otherwise recommended.
Applicability	Web Application Server
Example	<filter></filter>
	<filter-name>Browser Cache Filter</filter-name>
	<pre><filter- class="">com.splwg.base.web.services.BrowserCacheFilter</filter-></pre>
	class>
	<init-param></init-param>
	<param-name>maxAge</param-name>
	<param-value>28850</param-value>

A.3.5 auth-method - Authorization Method

Parameter	auth-method
Description	Sets the <u>JEE authentication method</u> for the product.
Ordinality	Mandatory
Valid Values	[BASIC CLIENT-CERT FORM]
Source	Derived from WEB_WLAUTHMETHOD - Authentication Method parameter from ENVIRON.INI. Depending on the value this may lead to further settings being implemented. BASIC - Enables the operating system to provide the logon dialog. CLIENT-CERT - Enables an external solution such as a SSO solution, Kerberos or any security implementing client certificates to provide credentials. DIGEST - Use digest authentication Note: Not supported for an external LDAP provider or custom provider within Oracle Webl original Pigest Authentication is only supported if SID is installed with
	Oracle WebLogic. Digest Authentication is only supported if SIP is installed with Oracle WebLogic. FORM - This instructs the product to implement the following additional settings: WEB_FORM_LOGIN_PAGE — Default Form Login Page and WEB_FORM_LOGIN_ERROR_PAGE — Default Form Login Error Page need to be set to indicate the form to use for online authentication.
Applicability	Web Application Server
Example	<login-config> </login-config>

A.3.6 fieldValuesAge - Server Cache Lifetime

Parameter	fieldValuesAge
Description	Set the duration (in seconds) to hold data in the server data cache.
Ordinality	Mandatory
Valid Values	1 - 2147483647
	Default: 3600
Source	Defaulted from template. Changes to the value require implementing a <u>custom</u> <u>template</u> .
Applicability	Web Application Server, Business Application Server
Example	<env-entry></env-entry>
	<pre><description>How long to cache drop down values in seconds</description></pre>
	<env-entry-name>fieldValuesAge</env-entry-name>
	<env-entry-type>java.lang.Integer</env-entry-type>
	<env-entry-value>3600</env-entry-value>

A.3.7 disableUIPageCompression - Disable UI Compression

Parameter	disableUIPageCompression
Description	Enables or disables compression between the browser and web application server (true or false).
Ordinality	Mandatory
Valid Values	[true false]
Source	Derived from <u>WEB_ISDEVELOPMENT</u> - Development Environment parameter from <u>ENVIRON.INI</u> . It is highly recommended to set to false for all environment exception is development environments using Oracle Utilities SDK.
Applicability	Web Application Server
Example	<pre><env-entry> <description>Disable UIPage compression</description> <env-entry-name>disableUIPageCompression</env-entry-name> <env-entry-type>java.lang.Boolean</env-entry-type> <env-entry-value>false</env-entry-value> </env-entry></pre>

A.4 spl.properties

Threadpool spl.properties file is used by each layer of the product to configure the technical aspects of the product behavior. All settings in this file are of the format:

<parameter>=<parameter value>

A.4.1 calendar.japanese.eras - Japanese Era Definition

Parameter	calendar.japanese.eras
Description	This is a set of strings defining the era used in the Japanese calendar. The string is a collection of the following tags (one set per era separated with a ";" delimiter): • name - Name of era • abbr - Era Abberviation • since - Date era starts in ISO format (YYYY-MM-DD) • endDate - Date era ends in ISO format (YYYY-MM-DD) • japAbbr - The Japanese character for the era in Unicode format Note: This feature is only appropriate if the Japanese language pack is also installed.
Ordinality	Mandatory
Valid Values	String set by implementations
Source	Value inherited from templates. Use <u>Implementing custom template</u> to set this value, if desired.
Applicability	Business Application Server, Background Processing
Example	calendar.japanese.eras=name:Taisho,abbr:T,since:1912-07-30,endDate:1926-12-24,japAbbr:\u5927\u6B63;name:Showa,abbr:S,since:1926-12-25,endDate:1989-01-07,japAbbr:\u662D\u548C;name:Heisei,abbr:H,since:1989-01-08,endDate:,japAbbr:\u5E73\u6210

A.4.2 com.oracle.ouaf.customer.whitelist.file – Customer's URL Allow List File

Parameter	com.oracle.ouaf.customer.whitelist.file
Description	Full directory path to the URL customer's allow list file to be checked for restricting URLs.
Ordinality	Optional
Valid Values	Location of allow list URL file, along with filename.
Source	Defaulted from the <u>CLOUD_CUSTOM_WHITE_LIST_PATH</u> value in <u>ENVIRON.INI</u> .
Applicability	Business Application Server
Example	com.oracle.ouaf.customer.whitelist.file=@SPLEBASE@/etc/cm_whitelist.xml The installed product base directory is defaulted from SPLEBASE value in ENVIRON.INI

A.4.3 com.oracle.ouaf.consolidatedLog.fileName – Consolidate Log File

Parameter	com.oracle.ouaf.consolidatedLog.fileName
Description	Full path to the consolidated log file to retrieve logs in clustered cloud environments.
Ordinality	Optional
Valid Values	Location of consolidate log file, along with filename.
Source	Defaulted from the CONSOLIDATED_LOG_DIR value in ENVIRON.INI.
Applicability	Business Application Server
Example	com.oracle.ouaf.consolidatedLog.fileName=@SPLEBASE@/etc/cm_whitelist .xml The installed product base directory is defaulted from SPLEBASE value in ENVIRON.INI

A.4.4 com.oracle.ouaf.dbms.scheduler.schema – DBMS Scheduler Object's Schema

Parameter	com.oracle.ouaf.dbms.scheduler.schema
Description	The DBMS scheduler objects will be created in the user/schema specified by the property. This property should match the schema where the DBMS integration package was installed in.
Ordinality	Optional
Valid Values	DB Schema name where DBMS integration package is installed.
Source	Defaulted from the value in ENVIRON.INI.
Applicability	Business Application Server
Example	com.oracle.ouaf.dbms.scheduler.schema=DBSchemaName

A.4.5 com.oracle.ouaf.file.tempstorage.dir – Location for Temporary File

Parameter	com.oracle.ouaf.file.tempstorage.dir
Description	The file being transferred using the file adapter API of OUAF will be split into multiple files and stored temporarily in this location.
Ordinality	Optional
Valid Values	Directory path on the server.
Source	Defaulted from the value in <u>ENVIRON.INI</u> .
Applicability	Business Application Server, Background Processing
Example	com.oracle.ouaf.file.tempstorage.dir=/ouaf/spl/tempdirectory

A.4.6 com.oracle.ouaf.file.tempstorage.splitfilesize – Split File Size in MB

Parameter	com.oracle.ouaf.file.tempstorage.splifilesize
Description	The file being transferred using the file adapter API of OUAF will be split into multiple files based on the size specified against this property.
Ordinality	Optional
Valid Values	Size in MB. Default is 50
Source	Defaulted from the value in <u>ENVIRON.INI</u>
Applicability	Business Application Server, Background Processing
Example	com.oracle.ouaf.file.tempstorage.splitfilesize=75

A.4.7 com.oracle.ouaf.groovy.precompile.allscripts - Enable Precompilation of Groovy Scripts

Parameter	com.oracle.ouaf.groovy.precompile.allscripts
Description	Enables the precompilation of groovy scripts during application startup.
Ordinality	Mandatory
Valid Values	[true false]
Source	Value inherited from templates. Use custom template to set this value, if desired.
Applicability	Business Application Server
Example	com.oracle.ouaf.groovy.precompile.allscripts=true

A.4.8 com.oracle.ouaf.groovy.precompile.maxWaitTime - Max Wait Time for Groovy Scripts Precompilation

Parameter	com.oracle.ouaf.groovy.precompile.maxWaitTime
Description	Sets maximum wait time to precompile the pre-configured groovy scripts
Ordinality	Mandatory
Valid Values	Value in milliseconds
Source	Value inherited from templates. Use custom template to set this value, if desired.
Applicability	Business Application Server
Example	com.oracle.ouaf.groovy.precompile.maxWaitTime=30000

A.4.9 com.oracle.ouaf.migrationAssistant.exportDirectory – Directory for Exported CMA File

Parameter	com.oracle.ouaf.migrationAssistant.exportDirectory
Description	Contains a directory specification, using the defined substitution variable @F1_MIGR_ASSISTANT_FILES@, in the white list.
Ordinality	Optional
Valid Values	Location of the CMA export file on the server.
Source	Value inherited from templates. Use custom template to set this value.
Applicability	Business Application Server, Background Processing
Example	com.oracle.ouaf.migrationAssistant.exportDirectory=@F1_MIGR_ASSIST ANT_FILES@/export

A.4.10 com.oracle.ouaf.migrationAssistant.importDirectory – Directory for CMA File for Import

Parameter	com.oracle.ouaf.migrationAssistant.importDirectory
Description	Contains a directory specification, using the defined substitution variable @F1_MIGR_ASSISTANT_FILES@, in the white list.
Ordinality	Optional
Valid Values	Location of the CMA import file on the server.
Source	Value inherited from templates. Use custom template to set this value.
Applicability	Business Application Server, Background Processing
Example	com.oracle.ouaf.migrationAssistant.importDirectory=@F1_MIGR_ASSIST ANT_FILES@/import

A.4.11 com.oracle.ouaf.migrationAssistant.fileExtension – Extension of CMA File

Parameter	com.oracle.ouaf.migrationAssistant.fileExtension
Description	Specifies the file extension of the CMA file.
Ordinality	Optional
Valid Values	File Extensions.
Source	Value inherited from templates. Use custom template to set this value.
Applicability	Business Application Server, Background Processing
Example	com.oracle.ouaf.migrationAssistant.fileExtension=cma

A.4.12 com.oracle.ouaf.proxy.password – Proxy Credentials for Senders if JVM is Configured to Use Proxy

Parameter	com.oracle.ouaf.proxy.password
Description	Password corresponding to a username set using 'com.oracle.ouaf.proxy.user' property to utilize for senders when the jvm is configured to utilize proxy via variables like http.proxyHost and http.proxyPort.
Ordinality	Optional
Valid Values	Encrypted value obtained using keystore.
Source	Value inherited from templates. Use custom template to set this value.
Applicability	Business Application Server, Background Processing
Example	com.oracle.ouaf.proxy.password=Xds12312SA!@sdf

A.4.13 com.oracle.ouaf.proxy.user – Proxy Credentials for Senders if JVM is Configured to Use Proxy

Parameter	com.oracle.ouaf.proxy.user
Description	Plain text user name to utilize for senders when the jvm is configured to utilize proxy via variables like http.proxyHost and http.proxyPort.
Ordinality	Optional
Valid Values	Plain text user name.
Source	Value inherited from templates. Use custom template to set this value.
Applicability	Business Application Server, Background Processing
Example	com.oracle.ouaf.proxy.user=user1

A.4.14 com.oracle.ouaf.system.database.disableTagging - Disables Database Tagging

Parameter	com.oracle.ouaf.system.database.disableTagging
Description	This enables (false) or disables (true) the database connection tagging feature.
	Note: Disabling this feature can reduce monitoring capabilities, disable support for Oracle Audit Vault, disable session resource management in Oracle Real Application Clusters and disable advanced support for Database resource plans.
Ordinality	Mandatory
Valid Values	[true false]
Source	Value inherited from templates. Use Implementing Custom Template to set this value to true, if desired.
Applicability	Web Application Server, Business Application Server, Inbound Web Services, Background Processing
Example	com.oracle.ouaf.system.database.disableTagging=false

A.4.15 com.oracle.ouaf.ui.disableRequiredFieldIndicators – Disable Required Field Indicators on UI Map

Parameter	com.oracle.ouaf.ui.disableRequiredFieldIndicators
Description	Specifies if the required field indicators on the application UI map should be disabled.
Ordinality	Optional
Valid Values	[true false]
Source	Value inherited from templates. Use custom template to set this value
Applicability	Business Application Server
Example	com.oracle.ouaf.ui.disableRequiredFieldIndicators=true

A.4.16 com.oracle.ouaf.uriSubstitutionVariables.file – URI Predefined Variables List File

Parameter	com.oracle.ouaf.uriSubstitutionVariables.file
Description	Points to the file containing the predefined URI substitution variable list.
Ordinality	Mandatory for cloud installations. Optional for on premise installations.
Valid Values	Path of the URI substitution variable list file.
Source	Value inherited from <u>CLOUD SUBSTITUTION VARIABLE LIST FILE LOCATION</u> in the <u>ENVIRON.INI</u> file.
	The following substitution variables are provided by default in OUAF: 1. F1_CMA_FILES
	(The below variables are provided for this release but will be removed from future releases as these are not used in any product functionality.)
	2. F1_BI_EXTRACTS
	3. F1_INTERNAL_FILES
	4. F1_CUST_APP_BASE
	5. F1_PROCESS_DIR
	6. F1_SVC_CATALOG_WSDL_DIR
	7. F1_PDB_EXTRACTS
	8. F1_OPEN_API_BASE_URL
Applicability	Business Application Server
Example	com.oracle.ouaf.uriSubstitutionVariables.file=@SPLEBASE@/etc/substitutionVariableList.xml

A.4.17 com.oracle.ouaf.uriValidation.enable – Enable Restriction of URLs

Parameter	com.oracle.ouaf.uriValidation.enable
Description	Enable URL validation. Restricts external URLs based on white list filename.
Ordinality	Mandatory for cloud installations. Optional for on premise installations.
Valid Values	[true false]. Default value is false
Source	Defaulted from the <u>CLOUD_RESTRICTION_URLS_ENABLE</u> value in <u>ENVIRON.INI</u> .
Applicability	Business Application Server
Example	com.oracle.ouaf.uriValidation.enable=false

A.4.18 com.oracle.ouaf.web.allowCORS - Enable Cross Origin Resource Sharing

Parameter	com.oracle.ouaf.web.allowCORS
Description	Enable Cross Origin Resource Sharing for UI emebedding.
Ordinality	Optional
Valid Values	[true false]
Source	Defined based on the parameter ENABLE_CORS being set in ENVIRON.INI.
Applicability	Web Application Server
Example	com.oracle.ouaf.web.allowCORS=false
	Note: Ensure that com.oracle.ouaf.web.disableSecureCookie should not be set to true.

A.4.19 com.oracle.ouaf.web.csp.enable - Enable Content Security Policy

Parameter	com.oracle.ouaf.web.csp.enable
Description	Enables or disables Content Security Policy response header.
Ordinality	Optional
Valid Values	[true false]
Source	Inherited from templates. Create custom template to update this setting.
Applicability	Web Application Server
Example	com.oracle.ouaf.web.csp.enable=true
	Note: Content Security Policy is enabled by default. To enable access to resources (such as javascript, CSS etc) from other sources, add the source/ sources using the menu option properties related to Content Security Policy or add corresponding user exit include files that hold the source domain details, under \$SPLEBASE/templates folder. Content Security Policy can be disabled by setting this value to false.

A.4.20 com.oracle.ouaf.web.cspReporting.enable - Enable Content Security Policy reporting

Parameter	com.oracle.ouaf.web.cspReporting.enable
Description	Enables or disables Content Security Policy reporting to view the list of values that are expected to be included in Content Security Policy settings. The values can be viewed in the developer tools console of the web browser being used to access the application. The com.oracle.ouaf.web.csp.enable property should be set to false, when this is set to true.
Ordinality	Optional
Valid Values	[true false]
Source	Inherited from templates. Create custom template to update this setting.
Applicability	Web Application Server
Example	com.oracle.ouaf.web.cspReporting.enable=true

A.4.21 com.oracle.ouaf.web.csp.allowedFrameAnsMaxNum ber - Allowed Frame Ancestors Max Number

Parameter	com.oracle.ouaf.web.csp.allowedFrameAnsMaxNumber
Description	Maximum number of frame ancestors allows in Cross Origin Resource Sharing for UI embedding.
Ordinality	Optional
Valid Values	Numeric value
Source	Defined based on the parameter CORS_ALLOWED_FRAME_ANCESTORS_MAX_NUMBER being set ENVIRON.INI.
Applicability	Web Application Server
Example	com.oracle.ouaf.web.csp.allowedFrameAnsMaxNumber=2

A.4.22 com.oracle.ouaf.web.disableScreenHideSessionTime out- Disables Screen Hide on Session Timeout

Parameter	com.oracle.ouaf.web.disableScreenHideSessionTimeout
Description	Setting this to true disables the hiding of the application screen visibility upon user session timeout.
Ordinality	Optional
Valid Values	[true false]
Source	Inherited from templates. Create custom template to update this setting.
Applicability	Web Application Server
Example	com.oracle.ouaf.web.disableScreenHideSessionTimeout=false

A.4.23 com.oracle.ouaf.web.disableSecureCookie - Web Pages User Experience Style

Parameter	com.oracle.ouaf.web.disableSecureCookie
Description	Disables secure cookie in non-SSL environments
Ordinality	Optional
Valid Values	[true false]
Source	Defined based on the parameter WEB WLSSLPORT being set in ENVIRON.INI
Applicability	Web Application Server
Example	com.oracle.ouaf.WEB.userInterfaceStyle=REDWOOD

A.4.24 com.oracle.ouaf.web.userInterfaceStyle - Web Pages User Experience Style

Parameter	com.oracle.ouaf.web.userInterfaceStyle
Description	The style of user experience to be used for OUAF web pages. OUAF support Redwood user experience by default. Old style experience can be enabled by setting appropriate value.
Ordinality	Optional
Valid Values	REDWOOD - Redwood user experience, OPE - Old style user experience. Default: REDWOOD
Source	Defaulted from the USER_INTERFACE_STYLE value in ENVIRON.INI
Applicability	Web Application Server
Example	com.oracle.ouaf.WEB.userInterfaceStyle=REDWOOD

A.4.25 com.oracle.ouaf.web.oracleGuidedeLearningId - Oracle Guided Learning Identifier

Parameter	com.oracle.ouaf.web.oracleGuidedLearningId
Description	Identifier of Oracle Guided Learning for usage with OUAF application
Ordinality	Optional
Valid Values	Identifier of Oracle Guided Learning
Source	Defaulted from the ORACLE_GUIDED_LEARNING_ID value in ENVIRON.INI
Applicability	Web Application Server
Example	com.oracle.ouaf.web.oracleGuidedLearningId=4f3gf3sjf

A.4.26 com.oracle.ouaf.whitelist.file – Oracle URL Allow List Filename and Location

Parameter	com.oracle.ouaf.whitelist.file
Description	Full directory path to the URL oracle allow list file to be checked for restricting URIs.
Ordinality	Mandatory if restriction is activated.
Valid Values	Location of allow list URI file, along with filename.
Source	Defaulted from the CLOUD_WHITE_LIST_PATH value in ENVIRON.INI.
Applicability	Business Application Server
Example	com.oracle.ouaf.whitelist.file=@SPLEBASE@/etc/whitelist.xml

A.4.27 com.oracle.XPath.LRUSize - XPath Cache

Parameter	com.oracle.XPath.LRUSize
Description	Sets Maximum XPath queries cached used in Schema based objects.
Ordinality	Optional
Valid Values	0 - No queries cached, -1 - Unlimited (7k per query), Value - Number of queries.
Source	Uses XQUERIES_TO_CACHE - Size of XQuery Cache value in ENVIRON.INI
Applicability	Business Application Server, Background Processing
Example	com.oracle.XPath.LRUSize=2000

A.4.28 com.oracle.XPath.flushTimeout - XPath Flush

Parameter	com.oracle.XPath.flushTimeout
Description	Sets time (in seconds) to reset XPath cache.
Ordinality	Optional
Valid Values	0 - Never auto flush, Value - Time in seconds between flushes.
Source	Uses XQUERY CACHE FLUSH TIMEOUT - Cache Life for XQueries value in ENVIRON.INI
Applicability	Business Application Server, Background Processing
Example	com.oracle.XPath.flushTimeout=86400

A.4.29 com.splwg.batch.cluster.jvmName - Online Batch JVM Name

Parameter	com.splwg.batch.cluster.jvmName
Description	Sets name for monitoring purposes for online batch JVM for online submission. This value is not used by the runtime, just exposed to the JMX interface for categorization purposes.
Ordinality	Optional
Valid Values	Any string without embedded blanks.
Source	Use the spl.properties.root.exit.include user exit include files to set this value.
Applicability	Web Application Server
Example	com.splwg.batch.cluster.jvmName=onlineBatch

A.4.30 com.splwg.batch.scheduler.daemon - Online Submission Daemon

Parameter	com.splwg.batch.scheduler.daemon
Description	Enable or Disable the Batch Daemon for online submission. The Batch Daemon is used to detect Pending Batch Submission objects and send them to Batch Online servers. It is highly recommended to specify a value of false for Production environments.
	The Batch Daemon is only recommended to be used, set to true , in Testing, Development or Demonstration environments.
Ordinality	Mandatory
Valid Values	[true false]
Source	Derived from <u>BATCHDAEMON</u> - <u>Whether Online Batch Daemon is Enabled parameter</u> from <u>ENVIRON.INI</u> .
Applicability	Business Application Server
Example	com.splwg.batch.scheduler.daemon=false

A.4.31 com.splwg.grid.executionMode - Online Execution Mode

Parameter	com.splwg.grid.executionMode
Description	Sets the execution mode of the online Batch submission.
Ordinality	Mandatory
Valid Values	[THIN CLUSTERED]
Source	Derived from <u>BATCH MODE - Default Mode of Batch</u> parameter from <u>ENVIRON.INI</u> .
Applicability	Business Application Server
Example	com.splwg.grid.executionMode=CLUSTERED

A.4.32 com.splwg.grid.online.enabled - Online Batch Server

Parameter	com.splwg.grid.online.enabled
Description	Enable or Disable the Batch Server for online submission. The Batch Server is reponsible for managing and executing jobs allocated by the Batch Daemon. It is highly recommended to specify a value of false for Production environments.
	Note: The Batch Server is only recommended to be used in Testing, Development or Demonstration environments.
Ordinality	Mandatory
Valid Values	[true false]
Source	Derived from <u>BATCHENABLED</u> - <u>Whether Online Batch Server parameter is Enabled</u> from <u>ENVIRON.INI</u> .
Applicability	Business Application Server
Example	com.splwg.grid.online.enabled=false

A.4.33 com.splwg.grid.distThreadPool.threads.DEFAULT - Online Submission Threadpool

Parameter	com.splwg.grid.distThreadPool.threads.DEFAULT
Description	Maximum number of concurrent threads used to execute online submission.
	This setting is used in conjunction with the Online Batch Server setting.
Ordinality	Mandatory
Valid Values	1 - 1000.
	Default: 5
Source	Derived from <u>BATCHTHREADS</u> - <u>Number of Online Batch Server Threads</u> parameter from <u>ENVIRON.INI</u> .
Applicability	Business Application Server
Example	com.splwg.grid.distThreadPool.threads.DEFAULT=5

A.4.34 com.splwg.schema.newValidations.F1 - Set Behavior of Validations

Parameter	com.splwg.schema.newValidations.F1
Description	Sets behavior of schema validations. Internal use only. This is set by individual products and should not be altered unless otherwise instructed by Oracle Support.
Ordinality	Mandatory
Valid Values	[true false]
Source	Value inherited from templates. Use <u>Implementing Custom Templates</u> to set this value to <u>false</u> , if desired.
Applicability	Web Application Server, Business Application Server
Example	com.splwg.schema.newValidations.F1=true

A.4.35 jmx.remote.x.access.file - JMX Access Control

Parameter	jmx.remote.x.access.file
Description	Sets relative location of JMX access control file holding the valid user.
	Refer to <u>JMX Security</u> for more details.
Ordinality	Mandatory
Valid Values	Relative location of file from \$SPLEBASE/%SPLEBASE%. Defaults to scripts/ouaf.jmx.access.file
Source	Value inherited from templates. Use <u>Implementing Custom Templates</u> to set this value to the desired location and file, if desired.
Applicability	Web Application Server, Business Application Server
Example	jmx.remote.x.access.file=scripts/ouaf.jmx.access.file

A.4.36 jmx.remote.x.password.file - JMX Password Control

Parameter	jmx.remote.x.password.file
Description	Sets relative location of JMX password file holding the valid passwords for jmx.remote.x.access.file. Refer to JMX Security for more details.
Ordinality	Mandatory
Valid Values	Relative location of file from \$SPLEBASE/%SPLEBASE%. Defaults to scripts/ouaf.jmx.password.file
Source	Value inherited from templates. Use <u>Implementing Custom Templates</u> to set this value to the desired location and file, if desired.
Applicability	Web Application Server, Business Application Server
Example	jmx.remote.x.password.file=scripts/ouaf.jmx.password.file

A.4.37 oracle.ouaf.jmx.httpssl.flag - SSL Flag for JMX REST

Parameter	oracle.ouaf.jmx.httpssl.flag
Description	SSL flag setting for JMX REST. This needs to be set to true for SSL enabled REST.
Ordinality	Optional
Valid Values	[true false]
Source	Derived from JMX_HTTPSSL_FLAG parameter from ENVIRON.INI.
Applicability	Web Application Server, Business Application Server, Background Processing
Example	oracle.ouaf.jmx.httpssl.flag=false

A.4.38 oracle.ouaf.jmx.httpssl.keypair.passphrase - Keypair Passphrase for REST JMX

Parameter	oracle.ouaf.jmx.httpssl.keypair.passphrase
Description	Keypair passphrase for keystore used for REST JMX.
Ordinality	Optional. Required if oracle.ouaf.jmx.httpssl.flag is set to true.
Valid Values	Encrypted passphrase
Source	Derived from JMX_HTTPSSL_KEYPAIR_PASSPHRASE parameter from ENVIRON.INI.
Applicability	Web Application Server, Business Application Server, Background Processing
Example	oracle.ouaf.jmx.httpssl.keypair.passphrase=ENC(23Sd\$dv sdva@&sdgsdfg)

A.4.39 oracle.ouaf.jmx.httpssl.keystore.file.path - Keystore File Path for REST JMX

Parameter	oracle.ouaf.jmx.httpssl.keystore.file.path
Description	File path to the keystore used for REST JMX.
Ordinality	Optional. Required if oracle.ouaf.jmx.httpssl.flag is set to true.
Valid Values	File path
Source	Derived from JMX_HTTPSSL_KEYSTORE_FILE parameter from ENVIRON.INI.
Applicability	Web Application Server, Business Application Server, Background Processing
Example	oracle.ouaf.jmx.httpssl.keystore.file.path=/root/ keystoreDirectory/keystorefile

A.4.40 oracle.ouaf.jmx.httpssl.keystore.passphrase - Keystore Passphrase for REST JMX

Parameter	oracle.ouaf.jmx.httpssl.keystore.passphrase
Description	Passphrase for accessing keystore for REST JMX.
Ordinality	Optional. Required if oracle.ouaf.jmx.httpssl.flag is set to true.
Valid Values	Encrypted passphrase
Source	Derived from JMX_HTTPSSL_KEYSTORE_PASSPHRASE parameter from ENVIRON.INI.
Applicability	Web Application Server, Business Application Server, Background Processing
Example	oracle.ouaf.jmx.httpssl.keystore.passphrase=ENC(\$3gdij STR34%&@DFD43F\$F)

A.4.41 oracle.ouaf.jmx.httpssl.keystore.type - Keystore Type for REST JMX

Parameter	oracle.ouaf.jmx.httpssl.keystore.type
Description	Type of keystore used for REST JMX.
Ordinality	Optional. Required if oracle.ouaf.jmx.httpssl.flag is set to true.
Valid Values	Java supported keystore types. Default is JKS.
Source	Derived from JMX_HTTPSSL_KEYSTORE_TYPE parameter from ENVIRON.INI.
Applicability	Web Application Server, Business Application Server, Background Processing
Example	oracle.ouaf.jmx.httpssl.keystore.type=JKS

A.4.42 oracle.ouaf.jmx.httpssl.truststore.filepath Truststore File Path for REST JMX

Parameter	oracle.ouaf.jmx.httpssl.truststore.filepath
Description	File path to the trust store used for REST JMX.
Ordinality	Optional. Required if oracle.ouaf.jmx.httpssl.flag is set to true.
Valid Values	File path
Source	Derived from JMX_HTTPSSL_TRUSTSTORE_FILE parameter from ENVIRON.INI.
Applicability	Web Application Server, Business Application Server, Background Processing
Example	oracle.ouaf.jmx.httpssl.truststore.filepath=/root/ truststoreDirectory/truststorefile

A.4.43 oracle.ouaf.jmx.httpssl.truststore.passphrase - Truststore Passphrase for REST JMX

Parameter	oracle.ouaf.jmx.httpssl.truststore.passphrase
Description	Passphrase to the trust store used for REST JMX.
Ordinality	Optional. Required if oracle.ouaf.jmx.httpssl.flag is set to true.
Valid Values	Encrypted passphrase
Source	Derived from JMX_HTTPSSL_TRUSTSTORE_PASSPHRASE parameter from ENVIRON.INI.
Applicability	Web Application Server, Business Application Server, Background Processing
Example	oracle.ouaf.jmx.httpssl.truststore.passphrase=ENC(\$3gd ijSTR34%&@DFD43F\$F)

A.4.44 oracle.ouaf.jmx.httpssl.truststore.type - Truststore type for REST JMX

Parameter	oracle.ouaf.jmx.httpssl.truststore.type
Description	Passphrase to the trust store used for REST JMX.
Ordinality	Optional. Required if oracle.ouaf.jmx.httpssl.flag is set to true.
Valid Values	Java supported truststore types.
Source	Derived from JMX_HTTPSSL_TRUSTSTORE_TYPE parameter from ENVIRON.INI.
Applicability	Web Application Server, Business Application Server, Background Processing
Example	oracle.ouaf.jmx.httpssl.truststore.type=JKS

A.4.45 jmx.remote.x.password.file - JMX Password Control

Parameter	jmx.remote.x.password.file
Description	Sets relative location of JMX password file holding the valid passwords for jmx.remote.x.access.file. Refer to JMX Security for more details.
Ordinality	Mandatory
Valid Values	Relative location of file from \$SPLEBASE. Defaults to scripts/ouaf.jmx.password.file.
Source	Value inherited from templates. Use <u>Implementing Custom Templates</u> to set this value to the desired location and file, if desired.
Applicability	Web Application Server, Business Application Server.
Example	jmx.remote.x.password.file=scripts/ ouaf.jmx.password.file

A.4.46 oracle.ouaf.jmx.remote.startPort - JMX Override Port

Parameter	oracle.ouaf.jmx.remote.startPort
Description	Alternative port number for JMX monitoring. Allows for overrides from standard port. Overrides spl.runtime.management.rmi.port - JMX Port.
Ordinality	Optional
Valid Values	Valid port numbers. Defaults to spl.runtime.management.rmi.port - JMX Port
Source	Value inherited from templates. Use <u>implementing custom templates</u> to set this value to the desired location and file, if desired.
Applicability	Web Application Server, Business Application Server
Example	jmx.remote.x.password.file=scripts/ouaf.jmx.password.file

A.4.47 oracle.ouaf.jmx.rest.context - JMX REST Context

Parameter	oracle.ouaf.jmx.rest.context
Description	Server context for JMX REST server.
Ordinality	Optional
Valid Values	Valid context for JMX REST server.
Source	Derived from JMX_REST_CONTEXT parameter from ENVIRON.INI.
Applicability	Web Application Server, Business Application Server, Batch Processor
Example	oracle.ouaf.jmx.rest.context=amp

A.4.48 oracle.ouaf.jmx.rest.port.batch - Batch Server JMX Port Number for REST Server

Parameter	oracle.ouaf.jmx.rest.port.batch
Description	Port number of batch server JMX, for REST service.
Ordinality	Optional
Valid Values	Port number
Source	Derived from JMX_REST_PORT_BATCH parameter from ENVIRON.INI.
Applicability	Web Application Server, Business Application Server, Batch Processor
Example	oracle.ouaf.jmx.rest.port.batch=8080

A.4.49 oracle.ouaf.jmx.rest.port.service - Business Server JMX Port Number for REST Server

Parameter	oracle.ouaf.jmx.rest.port.service
Description	Port number of business server JMX, for REST service.
Ordinality	Optional
Valid Values	Port number
Source	Derived from JMX_REST_PORT_SERVICE parameter from ENVIRON.INI.
Applicability	Web Application Server, Business Application Server, Batch Processor
Example	oracle.ouaf.jmx.rest.port.service=8080

A.4.50 oracle.ouaf.jmx.rest.port.web - Web Server JMX Port Number for REST Server

Parameter	oracle.ouaf.jmx.rest.port.web
Description	Port number of web server JMX, for REST service.
Ordinality	Optional
Valid Values	Port number
Source	Derived from JMX_REST_PORT_WEB parameter from ENVIRON.INI.
Applicability	Web Application Server, Business Application Server, Batch Processor
Example	oracle.ouaf.jmx.rest.port.web=8080

A.4.51 oracle.ouaf.jmx.rest.service.flag - Enable/Disable REST Service for JMX

Parameter	oracle.ouaf.jmx.rest.service.flag
Description	Setting this to true enables REST service for JMX.
Ordinality	Optional
Valid Values	[true false]
Source	Derived from JMX_REST_SERVICE_FLAG parameter from ENVIRON.INI.
Applicability	Web Application Server, Business Application Server, Batch Processor
Example	oracle.ouaf.jmx.rest.service.flag=false

A.4.52 oracle.ouaf.jmx.rest.service.host - Hostname to Run the JMX REST Server

Parameter	oracle.ouaf.jmx.rest.service.host
Description	Fully qualified host name to run the JMX REST server.
Ordinality	Optional
Valid Values	Servers qualified hostname
Source	Derived from JMX_REST_SERVICE_HOST parameter from ENVIRON.INI.
Applicability	Web Application Server, Business Application Server, Batch Processor
Example	oracle.ouaf.jmx.rest.service.host=localhost

A.4.53 oracle.ouaf.malware.scan.host - Host URI for Attachment Malware Scanning

Parameter	oracle.ouaf.malware.scan.host
Description	URI for malware scanning of attachments.
Ordinality	Optional
Valid Values	URI
Source	Value inherited from ENVIRON.INI.
Applicability	Web Application Server, Business Application Server
Example	malwarescanner.custom.serveruri.com

A.4.54 oracle.ouaf.malware.scan.timeout - Timeout for Attachment Malware Scanning

Parameter	oracle.ouaf.malware.scan.timeout
Description	Timeout for custom malware scanning of attachments, i.e., the maximum wait time for completing the scan of an attachment using the malware scanner.
Ordinality	Optional
Valid Values	Time in seconds
Source	Value inherited from ENVIRON.INI.
Applicability	Web Application Server, Business Application Server
Example	20

A.4.55 ouaf.accessibility.features - Enable Accessibility Features

Parameter	ouaf.accessiblity.features
Description	Enables or disabled accessibility support from the product, specifically around implementing tablindex for column headers. Other accessibility features are not altered by this setting.
Ordinality	Mandatory
Valid Values	[true false]
Source	Value inherited from templates. Use <u>implementing custom templates</u> to set this value to <u>false</u> , if desired.
Applicability	Web Application Server
Example	ouaf.accessiblity.features=true

A.4.56 ouaf.attachment.disableSpecialCharCheckOnFileNa me - Disable Special Characters on File Name

Parameter	ouaf.attachment.disableSpecialCharCheckOnFileName
Description	Disables (true) or enables (false) check for special characters used in file name for attachment objects.
Ordinality	Mandatory
Valid Values	[true false]
Source	Value inherited from templates. Use <u>implementing custom templates</u> to set this value to true , if desired.
Applicability	Business Application Server
Example	ouaf.attachment.disableSpecialCharCheckOnFileName=false

A.4.57 ouaf.batch.onlineLogDir - Online Line Batch Log Directory

Parameter	ouaf.batch.onlineLogDir
Description	Sets the location of output from online batch submission and batch scheduler integration. If this property is set, batch logs will be accessible via the Batch Run Tree (application UI). Otherwise, the batch logs download link in the application will be disabled.
Ordinality	Optional
Valid Values	Valid location. Defaults to: \$SPLOUTPUT (%SPLOUTPUT% on Windows)
Source	Value inherited from <u>BATCH_ONLINE_LOG_DIR - Online Batch Submission Log Directory</u> from <u>ENVIRON.INI</u> .
Applicability	Background Processing
Example	ouaf.batch.onlineLogDir=/tmp

A.4.58 ouaf.batch.onlineLogDir.retain – Retain Online Line Batch Log Files

Parameter	ouaf.batch.onlineLogDir.retain
Description	Sets the total number of log files that are to be stored for each batch code and thread number. The log files for the particular batch code and thread number will be deleted except for the latest number of logs specified.
Ordinality	Optional
Valid Values	Number
Source	Generated by template. Use configuring batch using bedit to implement a different value.
Applicability	Background Processing
Example	ouaf.batch.onlineLogDir.retain=3
	The above example will keep the last three logs and delete the rest.

A.4.59 ouaf.database.session.setInstallationTimeZone - Set Time Zone for Sessions

Parameter	ouaf.database.session.setInstallationTimeZone
Description	Set this property to true if the Time Zone on the installation record via the online Installation Options - Framework menu item (under Main tab) is different to the default timezone on the database. This will ensure session timezone is corrected.
Ordinality	Mandatory
Valid Values	[true false]
Source	Value inherited from templates. Use <u>implementing custom template</u> to set this value to true , if desired.
Applicability	Business Application Server, Background Processing
Example	ouaf.database.session.setInstallationTimeZone=false

A.4.60 ouaf.flush.jms.disabled - Global Flush Supported

Parameter	ouaf.flush.jms.disabled
Description	Enables (false) or disables (true) global flush feature.
Ordinality	Optional
Valid Values	[true false]
Source	Value inherited from templates. Use <u>implementing custom template</u> to set this value to <u>false</u> , if desired.
Applicability	Web Application Server, Business Application Server, Inbound Web Services, Background Processing
Example	ouaf.flush.jms.disabled=true

A.4.61 ouaf.flush.jms.connection - Connection Factory for Global Flush

Parameter	ouaf.flush.jms.connection
Description	JNDI Name for Global JMS connection
Ordinality	Optional
Valid Values	Valid JNDI for JMS Connection Factory. Default: jms/OUFlushConnectionFactory
Source	Value inherited from templates. Use <u>implementing custom template</u> to set this value to an alternative value, if desired.
Applicability	Web Application Server, Business Application Server, Inbound Web Services, Background Processing
Example	ouaf.flush.jms.connection=jms/OUFlushConnectionFactory

A.4.62 ouaf.flush.jms.requestTopic - Global Flush Request Topic

Parameter	ouaf.flush.jms.requestTopic
Description	JNDI Name for Global JMS Request Topic
Ordinality	Optional
Valid Values	Valid JNDI for JMS Request Topic. Default: jms/OUFlushRequestTopic
Source	Value inherited from templates. Use <u>implementing custom template</u> to set this value to an alternative value, if desired.
Applicability	Web Application Server, Business Application Server, Inbound Web Services, Background Processing
Example	ouaf.flush.jms.requestTopic=jms/OUFlushRequestTopic

A.4.63 ouaf.flush.jms.responseTopic - Global Flush Response Topic

Parameter	ouaf.flush.jms.responseTopic
Description	JNDI Name for Global JMS Response Topic
Ordinality	Optional
Valid Values	Valid JNDI for JMS Response Topic. Default: jms/OUFlushResponseTopic
Source	Value inherited from templates. Use <u>implementing custom template</u> to set this value to an alternative value, if desired.
Applicability	Web Application Server, Business Application Server, Inbound Web Services, Background Processing, MOB
Example	ouaf.flush.jms.responseTopic=jms/OUFlushResponseTopic

A.4.64 ouaf.runtime.compatibility.enablePrecisionScaleOn Money - Money Processing

Parameter	ouaf.runtime.compatibility.enablePrecisionScaleOnMoney
Description	Enables or disabled precision checking on money fields.
Ordinality	Mandatory
Valid Values	[true false]
Source	Value inherited from templates. Use <u>implementing custom template</u> to set this value to <u>false</u> , if desired.
Applicability	Web Application Server
Example	ouaf.runtime.compatibility.enablePrecisionScaleOnMoney=false

A.4.65 ouaf.jmx.com.oracle.ouaf.ws.mbeans.WSFlushBean - WS Cache Flush

Parameter	ouaf.jmx.com.oracle.ouaf.ws.mbeans.WSFlushBean
Description	Enables or disables the Flush Mbean used for the online JMX monitoring. Refer to the Web Services JMX interface for more information. This parameter is only enabled if the JMX interface is enabled.
Ordinality	Mandatory
Valid Values	[enabled disabled]
Source	Value inherited from templates. Use <u>implementing custom template</u> to set this value to <u>disabled</u> , if desired.
Applicability	Inbound Web Services
Example	ouaf.jmx.com.oracle.ouaf.ws.mbeans.WSFlushBean=enabled

A.4.66 ouaf.jmx.com.splwg.base.support.management.mb ean.JVMInfo - JVM Information

Parameter	ouaf.jmx.com.splwg.base.support.management.mbean.JVMInfo
Description	Enables or disables the JVMInfo Mbean used for the online JMX monitoring.
	Refer to the Web Application Server JMX interface for more information.
	This parameter is only enabled if the JMX interface is enabled.
Ordinality	Mandatory
Valid Values	[enabled disabled]
Source	Value inherited from templates. Use <u>implementing custom template</u> to set this value to <u>disabled</u> , if desired.
Applicability	Web Application Server
Example	ouaf.jmx.com.splwg.base.support.management.mbean.JVMInfo=enabled

A.4.67 ouaf.jmx.com.splwg.base.web.mbeans.FlushBean - Manage Cache

Parameter	ouaf.jmx.com.splwg.base.web.mbeans.FlushBean
Description	Enables or disables the Mbean to reset the online data cache manually.
	Refer to the Web Application Server JMX interface for more information.
	This parameter is only enabled if the JMX interface is enabled.
Ordinality	Mandatory
Valid Values	[enabled disabled]
Source	Value inherited from templates. Use <u>implementing custom template</u> to set this value to <u>disabled</u> , if desired.
Applicability	Web Application Server
Example	ouaf.jmx.com.splwg.base.web.mbeans.FlushBean=enabled

A.4.68 ouaf.list.buffer.limit - List Iteration Limit

Parameter	ouaf.list.buffer.limit
Description	The number of iterations a list is allowed to be read before being truncated. A default of 30 is used, if none or an invalid value is specified for this property.
Ordinality	Optional
Valid Values	Value between 0 – 256: 30
Source	Value inherited from JEE container. Use <u>implementing custom template</u> to set this value, if alternative desired
Applicability	Business Application Server
Example	ouaf.list.buffer.limit=30

A.4.69 ouaf.messaging.transformerfactory - Transformer

Parameter	ouaf.messaging.transformerfactory
Description	Sets the transformation factory for the real time adapters. This parameter is only set if requested by Oracle Support.
Ordinality	Optional
Valid Values	Set to one of the following values: com.sun.org.apache.xalan.internal.xsltc.trax.TransformerFactoryImpl org.apache.xalan.xsltc.trax.TransformerFactoryImpl
Source	Value inherited from JEE container. Use <u>implementing custom template</u> to set this value, if alternative desired
Applicability	Business Application Server, Background Processing
Example	ouaf.messaging.transformerfactory=org.apache.xalan.xsltc.trax.TransformerFactoryImpl

A.4.70 ouaf.shortcut.ignore.altKeys - Disable Hot Keys

Parameter	ouaf.shortcut.ignore.altKeys
Description	Allows specific hot keys to be disabled to support specific keyboard layouts (e.g. Polish keyboards).
Ordinality	Optional
Valid Values	Comma separated list of keys to disable
Source	Set within template. Use the spl.properties.root.exit.include user exit include files to set this value.
Applicability	Web Application Server
Example	ouaf.shortcut.ignore.altKeys=C,L

A.4.71 ouaf.timeout.business_object.default - Set Default Business Object Timeout

Parameter	ouaf.timeout.business_object.default
Description	Sets the default timeout (in seconds) for Business Objects. Refer to the Online Transaction Timeouts for more information.
Ordinality	Optional
Valid Values	1 - 2147483647
Source	Use the spl.properties.service.timeouts.exit.include user exit include files to set this value as outlined in Online Transaction Timeouts.
Applicability	Business Application Server
Example	ouaf.timeout.business_object.default=10

A.4.72 ouaf.timeout.business_object.
 Specific Business Object Timeout

Parameter	ouaf.timeout.business_object. <bocode></bocode>
Description	Sets the timeout (in seconds) for Business Object designated by \leftrigoriangleriang
Ordinality	Optional
Valid Values	1 - 2147483647
Source	Use the spl.properties.service.timeouts.exit.include user exit include files to set this value as outlined in Online Transaction Timeouts.
Applicability	Business Application Server
Example	ouaf.timeout.business_object.CMUser=10

A.4.73 ouaf.timeout.business_service.default - Set Default Business Service Timeout

Parameter	ouaf.timeout.business_service.default
Description	Sets the default timeout (in seconds) for Business Services. Refer to the Online <u>Transaction Timeouts</u> for more information.
Ordinality	Optional
Valid Values	1 - 2147483647
Source	Use the spl.properties.service.timeouts.exit.include user exit include files to set this value as outlined in Online Transaction Timeouts.
Applicability	Business Application Server
Example	ouaf.timeout.business_service.default=10

A.4.74 ouaf.timeout.business_service.
 Specific Business Service Timeout

Parameter	ouaf.timeout.business_service. <bscode></bscode>
Description	Sets the timeout (in seconds) for Business Service designated by bscode which corresponds to the Business Service Name. This overrides the <u>ouaf.timeout.business service.default</u> setting for the indicated business service. Refer to the <u>Online Transaction Timeouts</u> for more information. To find valid values for Business Services, use the Business Service Maintenance function or use the following SQL: SELECT bus_svc_cd, descr FROM f1_bus_svc_l where language_cd = 'ENG'; The LANGUAGE_CD in the above query can be altered to other languages for language packs installed
Ordinality	Optional
Valid Values	1 - 2147483647
Source	Use the spl.properties.service.timeouts.exit.include user exit include files to set this value as outlined in Online Transaction Timeouts.
Applicability	Business Application Server
Example	ouaf.timeout.business_service.F1-EmailService=10

A.4.75 ouaf.timeout.query.default - Set Default Query Timeout

Parameter	ouaf.timeout.query.default
Description	Sets the default timeout (in seconds) for query zones (searches and lists). Refer to the Online Transaction Timeouts for more information.
	Use the Zone maintenance function to determine valid values.
	This setting only applies to the following zone types:
	F1-DE, F1-DE-MULQRY, F1-DE-QUERY and F1-DE-SINGLE
Ordinality	Optional
Valid Values	1 - 2147483647
Source	Use the spl.properties.service.timeouts.exit.include user exit include files to set this value as outlined in Online Transaction Timeouts.
Applicability	Business Application Server
Example	ouaf.timeout.query.default=10

A.4.76 ouaf.timeout.query.<zonecode> - Set Specific Query Timeout

Parameter	ouaf.timeout.query. <zonecode></zonecode>
Description	Sets the timeout (in seconds) for the online query zone designated by <zonecode> which corresponds to the Query Zone. This overrides the ouaf.timeout.query.default — Set Default Query Timeout setting for the indicated query zone. Refer to the Online Transaction Timeouts for more information. This setting only applies to the following zone types: F1-DE, F1-DE-MULQRY, F1-DE-QUERY and F1-DE-SINGLE Use the Zone maintenance function to determine valid values. Alternatively, it is possible to use SQL to fine the ZONE_CD's <zonecode>: SELECT z.zone cd, d.descr, z.zone hdl cd</zonecode></zonecode>
	FROM ci_zone z, ci_zone_l d
	WHERE z.zone_hdl_cd LIKE 'F1-DE%' AND z.zone_cd = d.zone_cd
	AND d.language_cd = 'ENG';
	The LANGUAGE_CD in the above query can be altered to other languages for language packs installed.
Ordinality	Optional
Valid Values	1 - 2147483647
Source	Use the spl.properties.service.timeouts.exit.include user exit include files to set this value as outlined in Online Transaction Timeouts.
Applicability	Business Application Server
Example	ouaf.timeout.business_service.F1-MSTCFGLS=10

A.4.77 ouaf.timeout.script.default - Set Default Script Timeout

Parameter	ouaf.timeout.script.default
Description	Sets the default timeout (in seconds) for Scripts. Refer to the Online
	<u>Transaction Timeouts</u> for more information.
Ordinality	Optional
Valid Values	1 - 32767
Source	Use the spl.properties.service.timeouts.exit.include user exit include files to set this value as outlined in Online Transaction Timeouts.
Applicability	Business Application Server
Example	ouaf.timeout.script.default=10

A.4.78 ouaf.timeout.script.<scriptname> - Set Specific Script Timeout

Parameter	ouaf.timeout.script. <scriptname></scriptname>
Description	Sets the timeout (in seconds) for Scripts designated by scriptname which corresponds to the Script Name. This overrides the <u>ouaf.timeout.script.default</u> <u>Set Default Script Timeout</u> setting for the indicated script. Refer to the <u>Online Transaction Timeouts</u> for more information.
	Note: This timeout does not apply to plug-in scripts.
	To find valid values for Script, use the Script Maintenance function or use the following SQL:
	SELECT s.scr_cd, d.descr254
	FROM ci_scr s, ci_scr_l d where s.scr_cd = d.scr_cd
	and s.scr_type_flg in ('BPSC','SVSC')
	and d.language_cd = 'ENG';
	The LANGUAGE_CD in the above query can be altered to other languages for language packs installed
Ordinality	Optional
Valid Values	1 - 2147483647
Source	Use the spl.properties.service.timeouts.exit.include user exit include files to set this value as outlined in Online Transaction Timeouts.
Applicability	Business Application Server
Example	ouaf.timeout.script.F1-ViewWSDL=10

A.4.79 ouaf.timeout.service.default - Set Default Service Timeout

Parameter	ouaf.timeout.service.default
Description	Sets the default timeout (in seconds) for Application Services. Refer to the Online Transaction Timeouts for more information.
Ordinality	Optional
Valid Values	1 - 2147483647
Source	Use the spl.properties.service.timeouts.exit.include user exit include files to set this value as outlined in Online Transaction Timeouts.
Applicability	Business Application Server
Example	ouaf.timeout.service.default=10

A.4.80 ouaf.timeout.service.<service> - Set Specific Service Timeout

Parameter	ouaf.timeout.service. <service></service>
Description	Sets the timeout (in seconds) for Application Services designated by <service> which corresponds to the Application Service Name. This overrides the ouaf.timeout.service.default – Set Default Service Timeout setting for the indicated Application Service. Refer to the Online Transaction Timeouts for more information.</service>
	To find valid values for Application Service, use the Application Service Maintenance function or use the following SQL:
	SELECT SVC_NAME, DESCR from CI_MD_SVC_L where language_cd = 'ENG';
	The LANGUAGE_CD in the above query can be altered to other languages for language packs installed.
Ordinality	Optional
Valid Values	1 – 2147483647
Source	Use the spl.properties.service.timeouts.exit.include <u>user exit</u> to set this value as outlined in <u>Online Transaction Timeouts</u> .
Applicability	Business Application Server
Example	ouaf.timeout.service.CILTUSEP=10

A.4.81 ouaf.web.appViewer.coreAppURL - AppViewer Callback URL

Parameter	ouaf.web.appViewer.coreAppURL
Description	URL for AppViewer to navigate back to the product.
Ordinality	Mandatory
Valid Values	Generated URL from <u>WEB_WLHOST - Web_Server_Host</u> , <u>WEB_WLPORT - Web_Server_HTTP_Port</u> , <u>WEB_WLSSLPORT - Oracle_WebLogic_SSL_HTTP_Port</u> and <u>WEB_CONTEXT_ROOT - Web_Context_Root</u>
Source	Value inherited from templates. Use <u>implementing custom template</u> to set this value to desired value.
Example	ouaf.web.appViewer.coreAppURL=http://localhost:6500/ouaf/loginPage.jsp#fromAppViewer

A.4.82 ouaf.web.disablePreload - Disable Screen Preload

Parameter	ouaf.web.disablePreload
Description	Enables or disables screen preloading at startup. Screens that are preloaded are auto loaded at startup rather than at first use, saving time at runtime for first use transactions. This parameter works in conjunction with ouaf.web.preloadAllPages — Preload Scope.
	It is highly recommended to set this value to false (default) for Production Environments. It is only suggested to set this to true in development environments that are used in conjunction with the Oracle Utilities SDK.
Ordinality	Mandatory
Valid Values	[true false]
Source	Derived from <u>WEB_ISDEVELOPMENT</u> — Development Environment parameter from <u>ENVIRON.INI</u> . It is highly recommended to set to the default unless otherwise recommended
Applicability	Web Application Server
Example	ouaf.web.help.coreAppURL=http://localhost:6500/ouaf/loginPage.jsp

A.4.83 ouaf.web.help.coreAppURL - Help Callback URL

Parameter	ouaf.web.help.coreAppURL
Description	URL for Help to navigate back to the product.
Ordinality	Mandatory
Valid Values	Generated URL from <u>WEB_WLHOST - Web Server Host</u> , <u>WEB_WLPORT - Web Server HTTP Port</u> , <u>WEB_WLSSLPORT - Oracle WebLogic SSL HTTP Port</u> and <u>WEB_CONTEXT_ROOT - Web Context Root</u>
Source	Value inherited from templates. Use <u>implementing custom templates</u> to set this value to desired value.
Applicability	Web Application Server
Example	ouaf.web.help.coreAppURL=//ouaf/loginPage.jsp

A.4.84 ouaf.web.helpRootURL - Help URL

Parameter	ouaf.web.helpRootURL
Description	URL for Help for help requests from online.
Ordinality	Mandatory
Valid Values	Generated URL from WEB_WLHOST - Web Server Host, WEB_WLPORT - Web Server HTTP Port, WEB_WLSSLPORT - Oracle WebLogic SSL HTTP Port and WEB_CONTEXT_ROOT - Web Context Root
Source	Value inherited from templates. Use <u>implementing custom templates</u> to set this value to desired value.
Applicability	Web Application Server
Example	ouaf.web.helpRootURL=/ouaf/help/

A.4.85 ouaf.web.JspHeader.maxAge - JSP Age

Parameter	ouaf.web.JspHeader.maxAge
Description	Set the duration (in seconds) to screen HTML, in the client cache, from the product on the client browser.
Ordinality	Mandatory
Valid Values	In accordance with JEE Standards Default: 28850
Source	Derived from <u>WEB MAXAGE</u> parameter from <u>ENVIRON.INI</u> . It is highly recommended to set to the default unless otherwise recommended.
Applicability	Web Application Server
Example	ouaf.web.JspHeader.maxAge=28850

A.4.86 ouaf.web.preloadAllPages - Preload Scope

Parameter	ouaf.web.preloadAllPages
Description	Set the scope of the preloading of pages. This parameter is only used if the

A.4.87 ouaf.web.useOHW - Use Oracle Help for Web Engine

Parameter	ouaf.web.useOHW
Description	Use the Oracle Help for Web engine rather than the legacy SPLHelp engine. This setting is only applicable to Oracle WebLogic customers.
Ordinality	Mandatory
Valid Values	[true false]
Source	Value inherited from templates. Use <u>implementing custom templates</u> to set this value to <u>false</u> , if desired.
Applicability	Web Application Server
Example	ouaf.web.useOHW=true

A.4.88 ouaf.weblogic.enableDiagnostics - Enable ECID Tracking

Parameter	ouaf.weblogic.enableDiagnostics
Description	Enables (true) or disable (false) ECID feature.
Ordinality	Mandatory
Valid Values	[true false]
Source	Value inherited from templates. Use <u>implementing custom templates</u> to set this value to true , if desired.
Applicability	Web Application Server
Example	ouaf.weblogic.enableDiagnostics=false

A.4.89 ouaf.webservices.security.defaultPolicy – IWS Customized Security Policy

Parameter	ouaf.webservices.security.defaultPolicy
Description	Sets the customized policy for the deployed IWS.
Ordinality	Mandatory
Valid Values	[true false]
Source	Value inherited from templates. Use <u>implementing custom templates</u> to set this value to <u>true</u> , if desired.
Applicability	Web Application Server
Example	ouaf.weblogic.enableDiagnostics=false

A.4.90 ouaf.ws.defaultUser - Default User for Web Services

Parameter	ouaf.ws.defaultUser
Description	Default user used for authorization for inbound web services if no credentials are provided on the web service call. This is provided for backward compatibility for XML Application Integration customers. It is recommended not to be set at all, as to enforce stronger security for web services.
Ordinality	Optional
Valid Values	Valid authorization user for product. A null or blank value enforces security on each web service call.
Source	Defaulted from templates. Use <u>implementing custom templates</u> to set this value to an alternative desired value.
Applicability	Inbound Web Services
Example	ouaf.ws.defaultUser=AUSER

A.4.91 ouaf.ws.deploy.appxml.file - Application XML File for Inbound Web Services

Parameter	ouaf.ws.deploy.appxml.file
Description	Location of the application.xml file for web services.
Ordinality	Man
Valid Values	Valid Path and location
Source	Derived from template. This should not be changed.
Applicability	Inbound Web Services
Example	ouaf.ws.deploy.appxml.file=/spl/ouaf/iws/resources/application.xml

A.4.92 ouaf.ws.deploy.ear - EAR File Name for Inbound Web Services

Parameter	ouaf.ws.deploy.ear
Description	Name of EAR file used for inbound web services
Ordinality	Optional
Valid Values	Valid authorization user for product. A null or blank value enforces security on each web service call.
Source	Derived from template Use <u>implementing custom templates</u> to set this value to an alternative desired value.
Applicability	Inbound Web Services
Example	ouaf.ws.deploy.ear=Webservices.ear

A.4.93 ouaf.ws.deploy.contextpath - Context Path for Inbound Web Services

Parameter	ouaf.ws.deploy.contextpath
Description	Default context path used for inbound web services calls
Ordinality	Optional
Valid Values	Valid authorization user for product. A null or blank value enforces security on each web service call.
Source	Derived from template Use <u>implementing custom templates</u> to set this value to an alternative desired value.
Applicability	Inbound Web Services
Example	ouaf.ws.deploy.contextpath=/ouaf/webservices/

A.4.94 ouaf.ws.pageService.annotations - Security Annotation for XAI Legacy services

Parameter	ouaf.ws.pageService.annotations
Description	The default security WS-Policy annotations attached for legacy page services (XAI) within IWS. To ensure backward compatibility, for customers using XAI legacy services, it is recommended to set this value to the default F1-USERNAM annotation.
Ordinality	Optional
Valid Values	Valid web service annotation
Source	Defaulted from templates. Use <u>implementing custom templates</u> to set this value to an alternative desired value.
Applicability	Inbound Web Services
Example	ouaf.ws.pageService.annotations=F1-USERNAM

A.4.95 ouaf.ws.superusers - Effective Web Services Users

Parameter	ouaf.ws.superusers
Description	Sets the effective users for inbound web services. This allows credentials from foreign systems to use credentials from the product. This is only set to alternatives if effective users are used.
Ordinality	Mandatory
Valid Values	Valid comma separated list of credentials
Source	Source Derived from WEB_SPLUSER parameter from ENVIRON.INI. Use implementing custom templates to set this value to an alternative desired value.
Applicability	Inbound Web Services
Example	ouaf.ws.superusers=SYSUSER

A.4.96 ouaf.ws.tools.artifact.generated.buildfile - Build File

Parameter	ouaf.ws.tools.artifact.generated.buildfile
Description	Location and name of ant build file used to generate the WAR file used for inbound web services. This setting is used by the iwsdeploy.sh – Inbound Web Services Deployment command as well as the online inbound web services deployment tool.
Ordinality	Mandatory
Valid Values	Location and name of build file. Defaults to \$SPLEBASE/splapp/iws/iws-build.xml (or %\$SPLEBASE%\splapp\iws\iws-build.xml on Windows)
Source	Derived from <u>SPLDIR – Home Directory of Product</u> parameter from <u>ENVIRON.INI</u> . Use <u>implementing custom templates</u> to set this value to an alternative desired value.
Applicability	Inbound Web Services
Example	ouaf.ws.tools.artifact.generated.buildfile=/spl/OUAFDEMO/splapp/iws/iws-build.xml

A.4.97 ouaf.ws.tools.artifact.generated.sourcedir - Location of generated source

Parameter	ouaf.ws.tools.artifact.generated.sourcedir
Description	Location of the source generated for inbound web services during the Web Services deployment process.
Ordinality	Mandatory
Valid Values	Location of generated source directory. Defaults to \$SPLEBASE/splapp/iws/gen (or %\$SPLEBASE%\splapp\iws\gen on Windows)
Source	Derived from <u>SPLDIR – Home Directory of Product</u> parameter from <u>ENVIRON.INI</u> . Use <u>implementing custom templates</u> to set this value to an alternative desired value.
Applicability	Inbound Web Services
Example	ouaf.ws.tools.artifact.generated.sourcedir=/spl/OUAFDEMO/splapp/iws/gen

A.4.98 ouaf.ws.tools.artifact.resource.dir - Location of Resources

Parameter	ouaf.ws.tools.artifact.resource.dir
Description	Location of the resource files used in the generation of inbound web services during the web services deployment process.
Ordinality	Mandatory
Valid Values	Location of resources used for inbound web services. Defaults to \$SPLEBASE/splapp/iws/resources (or %\$SPLEBASE%\splapp\iws\resources on Windows)
Source	Derived from <u>SPLDIR – Home Directory of Product</u> parameter from <u>ENVIRON.INI</u> . Use <u>implementing custom templates</u> to set this value to an alternative desired value.
Applicability	Inbound Web Services
Example	ouaf.ws.tools.artifact.resource.dir=/spl/OUAFDEMO/splapp/iws/resources

A.4.99 ouaf.ws.tools.artifact.schema.dir - Location of Schemas

Parameter	ouaf.ws.tools.artifact.schema.dir
Description	Location of the schema files used in the generation of inbound web services during the web services deployment process.
Ordinality	Mandatory
Valid Values	Location of schema files used for inbound web services. Defaults to \$SPLEBASE/splapp/xai/schemas (or %\$SPLEBASE%\splapp\xai\schemas on Windows)
Source	Derived from <u>SPLDIR – Home Directory of Product</u> parameter from <u>ENVIRON.INI</u> . Use <u>implementing custom templates</u> to set this value to an alternative desired value.
Applicability	Inbound Web Services
Example	ouaf.ws.tools.artifact.schema.dir=/spl/OUAFDEMO/splapp/xai/schemas

A.4.100 ouaf.ws.tools.artifact.xsl.dir - Web Service XSL Location

Parameter	ouaf.ws.tools.artifact.xsl.dir
Description	Location of the XSLT files used by inbound web services during the web services deployment process.
	This parameter can be overridden using the <u>ouaf.ws.xslDirOverride</u> – <u>Override</u> <u>XSL Location</u> setting.
Ordinality	Mandatory
Valid Values	Location of XSLT files used for inbound web services. Defaults to \$SPLEBASE/splapp/xai/schemas (or %\$SPLEBASE%\splapp\xai\schemas on Windows). By default, this value is shared with ouaf.ws.tools.artifact.schema.dir.
Source	Derived from <u>SPLDIR – Home Directory of Product</u> parameter from <u>ENVIRON.INI</u> . Use <u>implementing custom templates</u> to set this value to an alternative desired value.
Applicability	Inbound Web Services
Example	ouaf.ws.tools.artifact.xsl.dir=/spl/OUAFDEMO/splapp/xai/schemas

A.4.101 ouaf.ws.tracing - Inbound Web Services Tracing

Parameter	ouaf.ws.tracing
Description	Enable or Disable tracing for inbound web services.
Ordinality	Mandatory
Valid Values	[true false]
Source	Defaulted from templates. Use <u>implementing custom templates</u> to set this value to an alternative desired value.
Applicability	Inbound Web Services
Example	ouaf.ws.tracing=true

A.4.102 ouaf.ws.xslDirOverride - Override XSL Location

Parameter	ouaf.ws.xslDirOverride
Description	Location of the XSLT files used by inbound web services during the web services deployment process.
	This parameter overrides the <u>ouaf.ws.tools.artifact.xsl.dir – Web Service XSL Location</u> setting.
Ordinality	Mandatory
Valid Values	Valid directories on server containing xsl.
	For Microsoft Windows environments, use the file protocol.
Source	Not set. Use <u>implementing custom templates</u> to set this value to an alternative desired value.
Applicability	Inbound Web Services
Examples	ouaf.ws.xslDirOverride=/temp ouaf.ws.xslDirOverride=file:///c:/temp

A.4.103 spl.csv.delimiter.useFromDisplayProfile - List CSV Delimiter

Parameter	spl.csv.delimiter.useFromDisplayProfile
Description	Enables or disables the display of the delimiter for CSV upload/downloads from zones.
Ordinality	Mandatory
Valid Values	[true false]
Source	Derived from template. Use <u>implementing custom templates</u> to set this value to true , if desired.
Applicability	Web Application Server
Example	spl.csv.delimiter.useFromDisplayProfile=false

A.4.104 spl.ejbContainer.contextFactory - Context Factory for Business Application Server

Parameter	spl.ejbContainer.contextFactory
Description	Default JEE Context Factory to connect tiers.
Ordinality	Mandatory
Valid Values	Valid connection factory: Oracle WebLogic: weblogic.jndi.WLInitialContextFactory
Source	Derived from template. Use <u>implementing custom templates</u> to set this value to an alternative, if desired.
Applicability	Web Application Server, Inbound Web Services
Example	spl.ejbContainer.contextFactory=weblogic.jndi.WLInitialContextFactory

A.4.105 spl.ejbContainer.password - Password for Business Application Server

Parameter	spl.ejbContainer.password
Description	Default encrypted password for tier defined for business application server connections.
Ordinality	Mandatory
Valid Values	Valid password encrypted Administration user
Source	Oracle WebLogic: WEB_WLSYSPASS from ENVIRON.INI
	Use implementing custom templates to set this value to an alternative, if desired.
Applicability	Web Application Server, Inbound Web Services
Example	spl.ejbContainer.password=ENC(Hi7/RFy)

A.4.106 spl.ejbContainer.url - Business Application Server URL

Parameter	spl.ejbContainer.url
Description	URL to connect to the business application server from the Web.
	Application Server or inbound web services.
Ordinality	Mandatory
Valid Values	Valid URL for:
	Oracle WebLogic:
	t3:// <server>:<port> or t3s://<server>:<port></port></server></port></server>
Source	Derived from template. Use implementing custom templates to set this value to an alternative, if desired.
Applicability	Web Application Server, Inbound Web Services
Example	spl.ejbContainer.url=t3://localhost:6500

A.4.107 spl.ejbContainer.user - Business Application Server User

Parameter	spl.ejbContainer.user
Description	Administration user for business application server who can connect from the web application server and inbound Web Services.
Ordinality	Mandatory
Valid Values	Valid Administration User on JEE Server
Source	Oracle WebLogic: WEB_WLSYSUSER from ENVIRON.INI Use implementing custom templates to set this value to an alternative, if desired.
Applicability	Web Application Server, Inbound Web Services
Example	spl.ejbContainer.user=system

A.4.108 spl.geocodeDatasource.contextFactory - GIS Context Factory

Parameter	spl.geocodeDatasource.contextFactory
Description	Default JEE Context Factory to connect to GIS. This option will only be enabled if GIS is set to true in the ENVIRON.INI.
Ordinality	Mandatory
Valid Values	Valid connection factory: Oracle WebLogic: weblogic.jndi.WLInitialContextFactory
Source	Derived from template. Use implementing custom templates to set this value to an alternative, if desired.
Applicability	Web Application Server, Business Application Server, Background Processing
Example	spl.geocodeDatasource.contextFactory=weblogic.jndi.WLInitialContextFactory

A.4.109 spl.geocodeDatasource.password - GIS Connection Password

Parameter	spl.geocodeDatasource.password
Description	Encrypted password for GIS connection for spl.geocodeDatasource.user . This option will only be enabled if GIS is set to true in the

A.4.110 spl.geocodeDatasource.url - GIS Data Source

Parameter	spl.geocodeDatasource.url
Description	JNDI name for GIS Data Source. This option will only be enabled if GIS is set to true in the ENVIRON.INI.
Ordinality	Mandatory
Valid Values	Valid JNDI path for GIS Data Source
Source	Derived from GIS_WLSYSUSER from ENVIRON.INI
Applicability	Web Application Server, Business Application Server, Background Processing
Example	spl.geocodeDatasource.url=t3://localhost:7666/jdbc/gisdb

A.4.111 spl.geocodeDatasource.user - GIS Connection User

Parameter	spl.geocodeDatasource.user
Description	Valid JNDI user for GIS connection. This option will only be enabled if GIS is set to true in the ENVIRON.INI.
Ordinality	Mandatory
Valid Values	Encrypted password for GIS.
Source	Derived from GIS_WLSYSUSER from ENVIRON.INI
Applicability	Web Application Server, Business Application Server, Background Processing
Example	spl.geocodeDatasource.user=gisadmin

A.4.112 spl.runtime.compatibility.uiMapDisableInputValue - Map Defaults

Parameter	spl.runtime.compatibility.uiMapDisableInputValue
Description	Enables or disables compatibility behavior with Oracle Utilities Application Framework V2.1 in relation to blanking out default values in screens.
	Setting this value to true will emulate Oracle Utilities Application
	Framework V2.1 behavior.
	This setting is only applicable to customers who are upgrading from Oracle Utilities Application Framework V2.1 and wish to retain that behavior.
Ordinality	Optional
Valid Values	[true false]
Source	Manually set. Use user exit spl.properties.exit.include to set this value to true, if desired
Applicability	Web Application Server
Example	spl.runtime.compatibility.uiMapDisableInputValue=false

A.4.113 spl.runtime.compatibility.uiMapDropdownSelectFirs tValue – Drop-down defaults

Parameter	spl.runtime.compatibility.uiMapDropdownSelectFirstValue
Description	Enables or disables compatibility behavior with Oracle Utilities Application Framework V2.1 in relation to defaulting to the first value in dropdownlist. Setting this value to true will emulate Oracle Utilities Application Framework V2.1 behavior.
	This setting is only applicable to customers who are upgrading from Oracle Utilities Application Framework V2.1 and wish to retain that behavior.
Ordinality	Optional
Valid Values	[true false]
Source	Manually set. Use user exit spl.properties.exit.include to set this value to true, if desired
Applicability	Web Application Server
Example	spl.runtime.compatibility.uiMapDropdownSelectFirstValue=false

A.4.114 spl.runtime.compatibility.uiMapDisableTitle - Screen Title Defaults

Parameter	spl.runtime.compatibility.uiMapDisableTitle
Description	Enables or disables compatibility behavior with Oracle Utilities Application Framework V2.1 in relation to rendering screen titles.
	Setting this value to true will emulate Oracle Utilities Application
	Framework V2.1 behavior.
	This setting is only applicable to customers who are upgrading from Oracle Utilities Application Framework V2.1 and wish to retain that behavior.
Ordinality	Optional
Valid Values	[true false]
Source	Manually set. Use user exit spl.properties.exit.include to set this value to true, if desired
Source Applicability	

A.4.115 spl.runtime.compatibility.uiMapDisableGenerateUni queHtmlIDs - Map IDs

Parameter	spl.runtime.compatibility.uiMapDisableGenerateUniqueHtmllDs
Description	Enables or disables compatibility behavior with Oracle Utilities Application Framework V2.x in relation to generating a unique identifier's for HTML for duplicate elements in the screen. In Oracle Utilities Application Framework V2.x (true), duplicate HTML ids were permitted on screen elements. In Oracle Utilities Application Framework V4.x (false), unique ids are generated for screen elements by default.
	Setting this value to true will emulate Oracle Utilities Application Framework V2.x behavior.
	This setting is only applicable to customers who are upgrading from Oracle Utilities Application Framework V2.x and wish to retain that behavior.
Ordinality	Optional
Valid Values	[true false]
Source	Manually set. Use user exit spl.properties.exit.include to set this value to true, if desired
Applicability	Web Application Server
Example	spl.runtime.compatibility.uiMapDisableGenerateUniqueHtmlIDs=false

A.4.116 spl.runtime.customSQLSecurity – Enable SQL Allow List

Parameter	spl.runtime.customSQLSecurity
Description	Enables or disables SQL allow list validations for CM data explorer zones. Setting this to true will restrict the SQL in CM data explorer zone to the allow list. Setting this to false will not restrict the SQL in CM data explorer zones.
Ordinality	Mandatory
Valid Values	[true false]
Source	Manually set
Applicability	Web Application Server
Example	spl.runtime.customSQLSecurity=false

A.4.117 spl.runtime.disableCSRFProtection - Disable Security Tokens

Parameter	spl.runtime.disableCSRFProtection
Description	Enables or disables security token support for testing purposes with testing tools that do not support security tokens.
	It is highly recommended that this configuration setting be set to false in all environments, especially Production.
	It should only be set to true in testing environments where test tools are used and the test tool used does not support security tokens.
Ordinality	Optional
Valid Values	[true false]
Source	Manually set. Use user exit spl.properties.exit.include to set this value to true, if desired
Applicability	Web Application Server
Example	spl.runtime.disableCSRFProtection=false

A.4.118 spl.runtime.environ.init.dir - Location of Configuration Files

Parameter	spl.runtime.environ.init.dir
Description	Location of the configuration files used for the product. This is used to allow the product to read configuration files at runtime to determine behavior.
Ordinality	Mandatory
Valid Values	URL is derived from spl.runtime.environ.SPLEBASE with the etc directory appended.
Source	Derived from <u>cistab</u> file.
Applicability	Web Application Server, Business Application Server, Inbound Web Services
Example	spl.runtime.environ.init.dir=/spl/OUAFDEMO/etc

A.4.119 spl.runtime.environ.isWebExpanded - Expanded Mode

Parameter	spl.runtime.environ.isWebExpanded
Description	Determines whether WAR/EAR files are built [false] or as expanded directories [true]. The expanded mode is used for development purposes only and is only supported on Oracle WebLogic.
	It is recommended to set this to false to use WAR/EAR files for deployment.
Ordinality	Mandatory
Valid Values	[true false]
Source	Derived from WEB_ISEXPANDED parameter from ENVIRON.INI.
Applicability	Web Application Server, Business Application Server
Example	spl.runtime.environ.isWebExpanded=false

A.4.120 spl.runtime.environ.SPLEBASE - Location of Software

Parameter	spl.runtime.environ.SPLEBASE
Description	Home directory of the product installation
Ordinality	Mandatory
Valid Values	Full expanded directory on machine
Source	Derived from <u>cistab</u> file.
Applicability	Web Application Server, Business Application Server, Inbound Web Services, Background Processing
Example	spl.runtime.environ.SPLEBASE=/spl/OUAFDEMO

A.4.121 spl.runtime.initiatize.waittime - Start Time Delay

Parameter	spl.runtime.initialize.waittime
Description	Delay Time (in seconds) for start of application from initiation time. This is used to delay startup to ensure downstream connections are established prior to startup.
Ordinality	Optional
Valid Values	0 - 3000 (Default: 45)
Source	Derived from templates. Use implementing custom templates_to set this value to an alternative, if desired
Applicability	Inbound Web Services
Example	spl.runtime.initialize.waittime=45

A.4.122 spl.runtime.environ.SPLOUTPUT - Location of Output

Parameter	spl.runtime.environ.SPLOUTPUT
Description	Home directory of the product output
Ordinality	Mandatory
Valid Values	Full expanded directory on machine
Source	Derived from cistab - Global Configuration Files file.
Applicability	Web Application Server, Business Application Server, Inbound Web Services, Background Processing
Example	spl.runtime.environ.SPLEBASE=/spl/splapp/OUAFDEMO

A.4.123 spl.runtime.management.batch.cluster.url - Batch Cluster URL

Parameter	spl.runtime.management.batch.cluster.url
Description	URL for the Batch Cluster
Ordinality	Mandatory
Valid Values	Valid URL for Batch Cluster
Source	Derived from WEB_BATCH_CLUSTER_URL parameter from ENVIRON.INI.
Applicability	Web Application Server
Example	spl.runtime.management.batch.cluster.url=

A.4.124 spl.runtime.management.connector.url.default - JMX URL

Parameter	spl.runtime.management.connector.url.default
Description	JMX formatted URL to be used for JMX based monitoring.
Ordinality	Optional
Valid Values	URL is generated from the following settings:
	Web Application Server:
	WEB_WLHOST and WEB_IMX_RMI_PORT_PERFORMANCE
	Business Application Server:
	BSN_WLHOST and BSN_JMX_RMI_PORT_PERFORMANCE
	Inbound Web Services:
	BSN_WLHOST and BSN_JMX_RMI_PORT_PERFORMANCE
Source	Derived from ENVIRON.INI file.
Applicability	Web Application Server, Business Application Server, Inbound Web Services
Example	spl.runtime.environ.SPLEBASE=service:jmx:rmi:///jndi/rmi://localhost:1100
	/oracle/ouaf/ejbAppConnector

A.4.125 spl.runtime.management.rmi.port - JMX Port

Parameter	spl.runtime.management.rmi.port
Description	Port number to be used for JMX based monitoring.
Ordinality	Optional
Valid Values	Port number is generated from the following settings:
	Web Application Server
	WEB_JMX_RMI_PORT_PERFORMANCE
	Business Application Server
	BSN_JMX_RMI_PORT_PERFORMANCE
	Inbound Web Services
	BSN_JMX_RMI_PORT_PERFORMANCE
	Batch
	BATCH_RMI_PORT
Source	Derived from ENVIRON.INI file.
Applicability	Web Application Server, Business Application Server, Inbound Web Services
Example	spl.runtime.management.rmi.port=1100

A.4.126 spl.runtime.options.isFCFEnabled - RAC FCF Enabled

Parameter	spl.runtime.options.isFCFEnabled
Description	Enable or Disable RAC <u>Fast Connection Failover</u> support for database connections. Oracle Notification Services configuration is set by the <u>spl.runtime.options.onsserver=nodes – ONS Configuration parameter</u>
Ordinality	Mandatory
Valid Values	[true false]
Source	Derived from ONSCONFIG parameter from ENVIRON.INI.
Applicability	Business Application Server, Background Processing
Example	spl.runtime.options.isFCFEnabled=false

A.4.127 spl.runtime.options.onsserver=nodes - ONS Configuration

Parameter	spl.runtime.options.onsserver=nodes
Description	Specify the Oracle Notification Services (ONS) configuration for <u>Fast Connection</u> <u>Failover</u> support for database connections. Refer to the <u>Oracle Notification</u> <u>Services documentation</u> for details of ONS setup and values for this setting.
Ordinality	Mandatory
Valid Values	Valid ONS configuration string (without the nodes= prefix)
Source	Derived from ONSCONFIG parameter from ENVIRON.INI.
Applicability	Business Application Server, Background Processing
Example	spl.runtime.options.onsserver=nodes=racnode1:4200,racnode2:4200\nwa lletfile= /oracle11/onswalletfile

A.4.128 spl.runtime.options.allowSystemDateOverride - Set Testing Date

Parameter	spl.runtime.options.allowSystemDateOverride
Description	Allows the user of system test date override feature for testing. Refer to the Setting the Date for testing purposes for more information. It is highly recommended that this setting should be set to false in Production environments.
Ordinality	Mandatory
Valid Values	[true false]
Source	Manually set. Use custom templates to set this value to true, if desired.
Applicability	Web Application Server, Business Application Server
Example	spl.runtime.options.allowSystemDateOverride=false

A.4.129 spl.runtime.options.createSimpleWebAppContextEn able - Web Cache Loading

Parameter	spl.runtime.options.createSimpleWebAppContextEnable
Description	Enables or disables cache loading from web application server. Setting this value to true will load the server cache through the business application server. If the cache loading, is desired to be loaded within each tier then set this value to false. It is highly recommended that this setting should be set to true in Production environments.
Ordinality	Optional
Valid Values	[true false]
Valid Values Source	[true false] Manually set. Use user exit spl.properties.exit.include to set this value to false, if desired.
	Manually set. Use user exit spl.properties.exit.include to set this value to false, if

A.4.130 spl.runtime.options.isDevelopmentMode - Development Mode

Parameter	spl.runtime.options.isDevelopmentMode
Description	Enables or disables Development Mode for the product. Development mode disables and enables key features within the architecture to allow the Oracle Utilities SDK to be used optimally. The following settings are affected by this parameter:
	 Caching is disabled at all layers of the architecture. This can be renabled manually.
	 Screen Preloading is disabled. This can be renabled manually.
	 Compression is disabled at all layers of the architecture. This can be renabled manually.
	 The product is set to expanded mode to allow developers access to individual JEE objects rather than using WAR/EAR files.
	It is highly recommended that this setting should be set to false in
	Production environments.
	This setting is only set to true where the Oracle Utilities SDK is used directly.
Ordinality	Mandatory
Valid Values	[true false]
Source	Derived from WEB_ISDEVELOPMENT parameter from ENVIRON.INI.
Applicability	Web Application Server, Business Application Server, Inbound Web Services
Example	spl.runtime.options.isDevelopmentMode=false

A.4.131 spl.runtime.oracle.statementCacheSize - Java SQL Cache Size

Parameter	spl.runtime.oracle.statementCacheSize
Description	Number of SQL statement cached for Java based code.
	It is highly recommended not to alter this value unless otherwise advised by Oracle Support.
Ordinality	Mandatory
Valid Values	1 - 2147483647 (Default: 300)
Source	Derived from templates. Use implementing custom templates to set this value to an alternative, if desired
Applicability	Web Application Server, Business Application Server, Inbound Web Services
Example	spl.runtime.oracle.statementCacheSize=300

A.4.132 spl.runtime.performSignedNumberValidation.cprod uct> - Number Validation

Parameter	spl.runtime.performSignedNumberValidation. <pre>cproduct></pre>
Description	Unsigned Number Validation routine used by product. By default a F1 based routine is provided and this setting allows products to provide their own processing. This setting is provided for products only. Implementations should not set this value.
Ordinality	Optional
Valid Values	[true false]
Source	Derived from templates. Use <u>user exit</u> spl.properties.service.exit.include and spl.properties.standalone.exit.include to set this value to an alternative, if desired.
Applicability	Business Application Server, Background Processing
Example	spl.runtime.performSignedNumberValidation.F1=true

A.4.133 spl.runtime.service.extraInstallationServices - Installation Service

Parameter	spl.runtime.service.extraInstallationServices
Description	Specifies the internal service used for checking the installation records at startup time.
	This setting is used by the products, it is not recommended to be altered, unless otherwise directed by Oracle Support.
Ordinality	Optional
Valid Values	Service Name
Source	By default the service CILTINCP is used internally
Applicability	Web Application Server
Example	spl.runtime.service.extraInstallationServices=CILTINCP

A.4.134 spl.runtime.sql.highValue - SQL High Value

Parameter	spl.runtime.sql.highValue
Description	The high value used for parameters by SQL queries.
	It is highly recommended not to alter this value unless otherwise advised by Oracle Support.
Ordinality	Mandatory
Valid Values	Valid high value generated by installer.
Source	Derived from the HIGHVALUE setting in the ENVIRON.INI
Applicability	Web Application Server, Business Application Server, Background
	Processing
Example	spl.runtime.sql.highValue=\uF8FF

A.4.135 spl.runtime.utf8Database - UTF8 Support

Parameter	spl.runtime.utf8Database
Description	Enables or disables <u>UTF8</u> support within the product.
Ordinality	Mandatory
Valid Values	[true false]
Source	Derived from the ENCODING (CHAR_BASED_DB) setting in the ENVIRON.INI
Applicability	Web Application Server, Business Application Server, Background
	Processing
Example	spl.runtime.utf8Database=true

A.4.136 spl.runtime.warning.dialog.before.download - Enable Warning Message Before Data Download

Parameter	spl.runtime.warning.dialog.before.download
Description	Enables or disables the warning message display whenever user performs an action that causes data to be copied/downloaded to their local machine.
Ordinality	Optional
Valid Values	[true false]
Source	Derived from templates. Use <u>implementing custom templates</u> to set this value to an alternative, if desired
Applicability	Web Application Server
Example	spl.runtime.warning.dialog.before.download=true

A.4.137 spl.serviceBean.jndi.name - JNDI Name for Business Application Server

Parameter	spl.serviceBean.jndi.name
Description	JNDI name for business application server generated by installer. It is highly recommended not to alter this value unless otherwise advised by Oracle Support.
Ordinality	Mandatory
Valid Values	Generated by installer.
Source	Derived from the WEB_CONTEXT_ROOT setting in the ENVIRON.INI
Applicability	Web Application Server, Inbound Web Services
Example	spl.serviceBean.jndi.name=ouaf/servicebean

A.4.138 spl.tools.loaded.applications - Loaded Product

Parameter	spl.tools.loaded.applications
Description	List the internal product codes installed under the Oracle Utilities
	Application Framework.
	This setting is maintained by the individual products and should not be altered unless otherwise instructed by Oracle Support.
Ordinality	Mandatory
Valid Values	Comma separated list of products
Source	Maintained by product templates
Applicability	Web Application Server, Business Application Server, Inbound Web Services, Background Processing
Example	spl.tools.loaded.applications=base,cm

A.4.139 ouaf.propertyfile.usage – Properties Usage

Parameter	ouaf.propertyfile.usage
Description	Properties file module usage
Ordinality	Mandatory
Valid Values	root, rest, service, iws, standalone, tpw, xai
Source	Derived from templates
Applicability	Web Application Server, Business Application Server, Inbound Web Services, Background Processing
Example	ouaf.propertyfile.usage=root

A.5 hibernate.properties

The hibernate.properties file defines the connection to the database and the Object to Relational database mapping.

A.5.1 hibernate.cache.use_second_level_cache - Use Cache

Parameter	hibernate.cache.use_second_level_cache
Description	Enable or Disable the second level cache, which is enabled by default for classes which specifies a cache mapping. This is disabled by default as Oracle Utilities Application Framework includes its own cache.
Ordinality	Mandatory
Valid Values	[true false]
Source	Maintained by product templates. Use <u>implementing custom templates</u> to implement a different value.
Applicability	Business Application Server, Inbound Web Services, Background Processing
Example	hibernate.cache.use_second_level_cache=false

A.5.2 hibernate.connection.datasource - JNDI Data Source

Parameter	hibernate.connection.datasource
Description	Enables Data Source support and indicates JNDI data source. This is an alternative to UCP. See JNDI Data Sources for more information. JNDI data sources cannot be used for batch processing.
Ordinality	Mandatory
Valid Values	JNDI path to data source
Source	Maintained by product templates. Use <u>implementing custom templates</u> to implement a different value.
Applicability	Business Application Server, Inbound Web Services
Example	hibernate.connection.datasource=jdbc/ouafdb

A.5.3 hibernate.connection.driver_class - Connection Driver Class

Parameter	hibernate.connection.driver_class
Description	Driver class used by Hibernate.
Ordinality	Mandatory
Valid Values	Valid Driver Class. Default: oracle.jdbc.driver.OracleDriver
Source	Maintained by product templates. Use <u>implementing custom templates</u> to implement a different value.
Applicability	Business Application Server, Inbound Web Services, Background Processing
Example	hibernate.connection.driver_class=oracle.jdbc.driver.OracleDriver

A.5.4 hibernate.connection.password - Database User Password

Parameter	hibernate.connection.password
Description	Encrypted password for Database User.
Ordinality	Mandatory
Valid Values	Generated Database Password. Value depends on channel:
	Online uses DBPASS
	XAI/IWS uses XAI_DBPASS
	Batch uses BATCH_DBPASS
Source	Maintained by product templates. Set appropriate value for user required in required parameter.
Applicability	Business Application Server, Inbound Web Services, Background Processing
Example	hibernate.connection.password=ENCKS()

A.5.5 hibernate.connection.provider_class - Connection Provider

Parameter	hibernate.connection.provider_class
Description	Connection Provider Class for Hibernate. Use the default UCP provider as supplied unless using JBDC Data Sources where com.hibernate.connection.DatasourceConnectionProvider is used instead.
Ordinality	Mandatory
Valid Values	Generated Provider Class. Default: com.splwg.shared.common.UCPConnectionProvider
Source	Maintained by product templates. Use <u>implementing custom templates</u> to implement a different value.
Applicability	Business Application Server, Inbound Web Services, Background Processing
Example	hibernate.connection.provider_class=com.splwg.shared.common. UCPConnectionProvider

A.5.6 hibernate.connection.release_mode - Connection Release

Parameter	hibernate.connection.release_mode
Description	This parameter controls when a connection is released to the pool. By default the value is set to after_transaction. Whilst other values can be used, for consistency of the connection it is recommended to use the default.
Ordinality	Mandatory
Valid Values	Generated Release Mode. Default: after_transaction
Source	Maintained by product templates. Use <u>implementing custom templates</u> to implement a different value.
Applicability	Business Application Server, Inbound Web Services, Background Processing
Example	hibernate.connection.release_mode=after_transaction

A.5.7 hibernate.connection.url - JDBC URL

Parameter	hibernate.connection.url
Description	JDBC URL for connection to database.
Ordinality	Mandatory
Valid Values	Generated URL or using override database connection.
Source	Maintained by product templates. Use DB_OVERRIDE_CONNECTION for specific values.
Applicability	Business Application Server, Inbound Web Services, Background Processing
Example	hibernate.connection.url=jdbc:oracle:thin:@ouafdemo.us.oracle.com: 1522:/MYPDB

A.5.8 hibernate.connection.username - Database User

Parameter	hibernate.connection.username
Description	JDBC User for connection.
Ordinality	Mandatory
Valid Values	The value depends on the channel accessed:
	Online uses DBUSER
	IWS uses XAI_DBUSER
	Batch uses BATCH_DBUSER
Source	Maintained by product templates. Set appropriate value for user required in required parameter.
Applicability	Business Application Server, Inbound Web Services, Background Processing
Example	hibernate.connection.username=CISUSER

A.5.9 hibernate.dialect - Dialect Used

Parameter	hibernate.dialect
Description	This is the SQL dialect (database type) for the database being used. Any valid Hibernate dialect may be used. Refer to http://www.hibernate.org/hib_docs/v3/api/org/hibernate/dialect/package-summary.html for a full list.
Ordinality	Mandatory
Valid Values	Generated Dialect.
	Default: org.hibernate.dialect.Oracle10gDialect.
Source	Maintained by product templates. Use <u>implementing custom templates</u> to implement a different value.
Applicability	Business Application Server, Inbound Web Services, Background Processing
Example	hibernate.dialect=org.hibernate.dialect.Oracle10gDialect

A.5.10 hibernate.jdbc.batch_size - JDBC2 Update Support

Parameter	hibernate.jdbc.batch_size
Description	A non-zero value enables use of JDBC2 batch updates by Hibernate.
Ordinality	Mandatory
Valid Values	Generated Value. Default: 30
Source	Maintained by product templates. Use <u>implementing custom templates</u> to implement a different value.
Applicability	Business Application Server, Inbound Web Services, Background Processing
Example	hibernate.jdbc.batch_size=30

A.5.11 hibernate.jdbc.fetch_size - Solution Set Size

Parameter	hibernate.jdbc.fetch_size
Description	Determines a hint to the JDBC driver on the number of rows to return in any SQL statement. This is overridden at runtime on zone parameters and commit interval.
Ordinality	Mandatory
Valid Values	Generated Value. Default: 100
Source	Maintained by product templates. Use <u>implementing custom templates</u> to implement a different value.
Applicability	Business Application Server, Inbound Web Services, Background Processing
Example	hibernate.jdbc.fetch_size=100

A.5.12 hibernate.max_fetch_depth - Join Fetch Depth

Parameter	hibernate.max_fetch_depth
Description	Sets a maximum depth for the outer join fetch tree for single-ended associations (one-to-one, many-to-one). If you set the value to Zero (0), the default outer join fetching is disabled.
Ordinality	Mandatory
Valid Values	Generated Value. Default: 2
Source	Maintained by product templates. Use <u>implementing custom templates</u> to implement a different value.
Applicability	Business Application Server, Inbound Web Services, Background Processing
Example	hibernate.max_fetch_depth=2

A.5.13 hibernate.query.factory_class - HQL Parser

Parameter	hibernate.query.factory_class
Description	The classname of a Query Factory to use for HQL parsing.
Ordinality	Mandatory
Valid Values	Generated Value.
	Default: org.hibernate.hql.internal.classic.ClassicQueryTranslatorFactory
Source	Maintained by product templates. Use <u>implementing custom templates</u> to implement a different value.
Applicability	Business Application Server, Inbound Web Services, Background Processing
Example	hibernate.query.factory_class=org.hibernate.hql.internal.classic.ClassicQu eryTranslatorFactory

A.5.14 hibernate.query.substitutions - Literal Mappings

Parameter	hibernate.query.substitutions
Description	Mapping from tokens in Hibernate queries to SQL tokens (tokens might be function or literal names, for example).
Ordinality	Mandatory
Valid Values	Generated Value. Default: true 'Y', false 'N'
Source	Maintained by product templates. Use <u>implementing custom templates</u> to implement a different value.
Applicability	Business Application Server, Inbound Web Services, Background Processing
Example	hibernate.query.substitutions=true 'Y', false 'N'

A.5.15 hibernate.show_sql - Debug Mode

Parameter	hibernate.show_sql
Description	Use of Debug Mode for all SQL Statements. It is highly recommended not to enable debug at this level.
Ordinality	Mandatory
Valid Values	[true false]
Source	Maintained by product templates. Use <u>implementing custom templates</u> to implement a different value.
Applicability	Business Application Server, Inbound Web Services, Background Processing
Example	hibernate.show_sql=false

A.5.16 hibernate.transaction.factory_class - Transaction Class

Parameter	hibernate.transaction.factory_class
Description	The classname of a Transaction Factory to use with Hibernate Transaction
	API.
Ordinality	Mandatory
Valid Values	Generated Value.
	Default: org.hibernate.transaction.JDBCTransactionFactory.
Source	Maintained by product templates. Use <u>implementing custom templates</u> to implement a different value.
Applicability	Business Application Server, Inbound Web Services, Background Processing
Example	hibernate.transaction.factory_class=org.hibernate.transaction.JDBCTransactionFactory

A.5.17 hibernate.ucp.connection_wait_timeout - UCP Connection Timeout

Parameter	hibernate.ucp.connection_wait_timeout
Description	Specifies how long, in seconds, an application request waits to obtain a connection if there are no longer any connections in the pool
Ordinality	Mandatory
Valid Values	Generated Value. Default: 5
Source	Maintained by product templates. Use <u>implementing custom templates</u> to implement a different value.
Applicability	Business Application Server, Inbound Web Services, Background Processing
Example	hibernate.ucp.connection_wait_timeout=5

A.5.18 hibernate.ucp.inactive_connection_timeout - Connection Inactivity Timeout

Parameter	hibernate.ucp.inactive_connection_timeout
Description	Specifies how long, in seconds, an available connection can remain idle before it is closed and removed from the pool.
Ordinality	Mandatory
Valid Values	Generated Value. Default: 300
Source	Maintained by product templates. Use <u>implementing custom templates</u> to implement a different value.
Applicability	Business Application Server, Inbound Web Services, Background Processing
Example	hibernate.ucp.inactive_connection_timeout=300

A.5.19 hibernate.ucp.jmx_enabled - Enable UCP JMX

Parameter	hibernate.ucp.jmx_enabled
Description	Enable or Disable JMX Mbeans for UCP. The Mbeans will appear as additional classes on the existing JMX capabilities for that tier.
Ordinality	Mandatory
Valid Values	[true false]
Source	Maintained by product templates. Use <u>implementing custom templates</u> to implement a different value.
Applicability	Business Application Server, Inbound Web Services, Background Processing
Example	hibernate.ucp.jmx_enabled=false

A.5.20 hibernate.ucp.max_size - Maximum Pool Size

Parameter	hibernate.ucp.max_size
Description	Maximum Pool size for this tier. Maximum number of active connections to the database.
Ordinality	Mandatory
Valid Values	Generated. Default: 30
Source	Maintained by product templates. Use <u>implementing custom templates</u> to implement a different value.
Applicability	Business Application Server, Inbound Web Services, Background Processing
Example	hibernate.ucp.max_size=30

A.5.21 hibernate.ucp.max_statements - SQL Buffer Size

Parameter	hibernate.ucp.max_statements
Description	Number of statements cached for performance on this tier.
Ordinality	Mandatory
Valid Values	Generated. Default: 50
Source	Maintained by product templates. Use <u>implementing custom templates</u> to implement a different value.
Applicability	Business Application Server, Inbound Web Services, Background Processing
Example	hibernate.ucp.max_statements=50

A.5.22 hibernate.ucp.min_size - Minimum Pool Size

Parameter	hibernate.ucp.min_size
Description	Initial Connection Pool size for this tier.
Ordinality	Mandatory
Valid Values	Generated. Default: 1
Source	Maintained by product templates. Use <u>implementing custom templates</u> to implement a different value.
Applicability	Business Application Server, Inbound Web Services, Background Processing
Example	hibernate.ucp.min_size=1

A.6 submitbatch.properties (BATCH)

The submitbatch properties controls the behavior of individual batch job threads within the batch architecture. This configuration file exists in two forms:

- A global submitbatch.properties that defines global defaults for the implementation.
- A set of submitbatch.properties files for individual jobs that defines any configuration overrides or specific configuration settings for an individual job.

This section outlines each setting for the configuration file.

Note: It is recommended to use the <u>Configuring Batch Using Bedit</u> configuration utility to maintain this configuration file.

A.6.1 coherence.management.remote - Enable/Disable Remote Management of Cluster Members

Parameter	coherence.management.remote
Description	Property of Oracle Coherence. Enables/Disables remote management.
	Note: The coherence parameter: tangosol.coherence.management may be set to 'none' in submitbatchjob.properties, in conjunction with coherence.management.remote property set to false, to improve performance with JMX client console.
Ordinality	Optional
Valid Values	[true false]
Source	Maintained by product templates.
Applicability	Background Processing
Example	Coherence.management.remote=false

A.6.2 com.ouaf.batch.jvmoptions - JVM Options

Parameter	com.ouaf.batch.jvmoptions
Description	Custom JVM Options for submitter.
	Note: This setting can be overridden using the -z option on the <u>submitjob.sh</u> – <u>Submit Batch Threads</u> command line.
Ordinality	Mandatory
Valid Values	Valid JVM Options for the Java version used
Source	Maintained by product templates. Use <u>Configuring Batch Using Bedit</u> to implement a different value.
Applicability	Background Processing
Example	com.ouaf.batch.jvmoptions=-Xms1024k -Xmx2048k - XX:MaxPermSize=512m

A.6.3 com.splwg.grid.executionMode - Mode of Execution

Parameter	com.splwg.grid.executionMode
Description	Execution Mode used by process.
	Note: This setting can be overridden using the -e option on the <u>submitjob.sh</u> – <u>Submit Batch Threads</u> command line.
Ordinality	Mandatory
Valid Values	[CLUSTERED THIN]
	Note: The THIN mode is used by the Oracle Utilities SDK and should not be used outside that tool.
Source	Maintained by product templates. Use <u>implementing custom templates</u> to implement a
	Different value.
Applicability	Background Processing
Example	com.splwg.grid.executionMode=CLUSTERED

A.6.4 com.splwg.batch.submitter - THIN Submitter

Parameter	com.splwg.batch.submitter
Description	Whether this execution can run without a threadpoolworker. Reserved for development of batch using the Oracle Utilities SDK. If set to true then, com.splwg.grid.executionMode – Online Execution Mode must be set to THIN.
Ordinality	Mandatory
Valid Values	[false true]
Source	Maintained by product templates for LOCAL submission.
Applicability	Background Processing
Example	com.splwg.batch.submitter=true

A.6.5 com.splwg.batch.submitter.batchCd - Batch Code

Parameter	com.splwg.batch.submitter.batchCd
Description	Batch Code for batch specific configuration. This setting should not be set in the global <u>submitbatch.properties</u> file.
	Note: This setting should only be set in configuration files for testing purposes. In other situations the -b option on the <u>submitjob.sh — Submit Batch Threads</u> command line should be used.
Ordinality	Mandatory
Valid Values	Batch Code
Source	Maintained by product templates for submission.
Applicability	Background Processing
Example	com.splwg.batch.submitter.batchCd=QABATCH

A.6.6 com.splwg.batch.submitter.distThreadPool - Threadpool

Parameter	com.splwg.batch.submitter.distThreadPool
Description	Name of pool to be used for batch process. If threadpoolworker not used then LOCAL must be specified. This can be set globally and at the individual batch job level.
	Note: This setting can be overridden using the -p option on the <u>submitjob.sh – Submit Batch Threads</u> command line.
Ordinality	Mandatory
Valid Values	Default: DEFAULT
Source	Maintained by product templates. Use <u>implementing custom templates</u> to implement a different value.
Applicability	Background Processing
Example	com.splwg.batch.submitter.distThreadPool=DEFAULT

A.6.7 com.splwg.batch.submitter.languageCd - Language Code

Parameter	com.splwg.batch.submitter.languageCd
Description	Language code used for messages for execution of background process. Relevant language pack must be installed.
	Note: This setting can be overridden using the -I option on the submitjob.sh – Submit Batch Threads command line.
Ordinality	Mandatory
Valid Values	Default: ENG
Source	Maintained by product templates. Use <u>implementing custom templates</u> to implement a different value.
Applicability	Background Processing
Example	com.splwg.batch.submitter.languageCd=ENG

A.6.8 com.splwg.batch.submitter.maximumCommitRecor ds - Commit Interval

Parameter	com.splwg.batch.submitter.maximumCommitRecords
Description	Commit Interval used for execution. This is the number of objects processed per work unit.
	Note: This setting can be overridden using the -f option on the submitjob.sh – Submit Batch Threads command line.
Ordinality	Mandatory
Valid Values	Job specific
Source	Maintained by product templates. Use <u>implementing custom templates</u> to implement a different value.
Applicability	Background Processing
Example	com.splwg.batch.submitter.maximumCommitRecords=200

A.6.9 com.splwg.batch.submitter.promptForValues - Prompt for Values

Parameter	com.splwg.batch.submitter.promptForValues
Description	Prompt for value when running in interactive mode. This is primarily used for developers who are testing their job manually.
	Note: Implementers should only use the true value if executing jobs from the Oracle Utilities SDK.
Ordinality	Mandatory
Valid Values	[true false]
Source	Maintained by product templates. Use <u>implementing custom templates</u> to implement a different value.
Applicability	Background Processing
Example	com.splwg.batch.submitter.promptForValues=false

A.6.10 com.splwg.batch.submitter.processDate - Business Date

Parameter	com.splwg.batch.submitter.processDate
Description	Business Date for batch process. This setting should not be set in the global submitbatch.properties file.
	Note: This setting should only be set in configuration files for testing purposes. In other situations the -d option on the <u>submitjob.sh — Submit Batch Threads</u> command line should be used.
Ordinality	Mandatory
Valid Values	Business Date in ISO YYYY-MM-DD format
Source	Maintained by product templates for submission.
Applicability	Background Processing
Example	com.splwg.batch.submitter.processDate=2015-03-08

A.6.11 com.splwg.batch.submitter.rerunNumber - Re Run Number

Parameter	com.splwg.batch.submitter.rerunNumber
Description	Rerun Number to be used for execution.
	Note: Only batch controls that support rerun numbers are supported with this configuration setting. This setting can be overridden using the -r option on the submitjob.sh - Submit Batch Threads command line.
Ordinality	Optional
Valid Values	Valid run number. A value of zero (0) denotes disables this setting.
Source	Maintained by product templates. Use <u>implementing custom templates</u> to implement a different value.
Applicability	Background Processing
Example	com.splwg.batch.submitter.rerunNumber=56

A.6.12 com.splwg.batch.submitter.softParameter - Job Parameters

Parameter	com.splwg.batch.submitter.softParameter
Description	For any program-specific parameters, use this form of property specification in the format: com.splwg.batch.submitter.softParameter. <parameter.< p=""> The <parameter a="" of="" p="" program:<="" rows="" skip="" submitting="" to="" validation="" when=""> com.splwg.batch.submitter.softParameter.SKIP-ROWS=1000 Multiple soft parameters may be specified. Note: This setting can be overridden using the -x or -X options on the submitjob.sh command line.</parameter></parameter.<>
Ordinality	Mandatory
Valid Values	Valid value for parameter
Source	Maintained by product templates for submission.
Applicability	Background Processing
Example	com.splwg.batch.submitter.softParameter.SKIP-ROWS=1000

A.6.13 com.splwg.batch.submitter.threadCount - Thread Limit

Parameter	com.splwg.batch.submitter.threadCount
Description	Thread limit used for execution.
	Note: Only batch controls that support multithreaded are supported with this configuration setting.
	This setting can be overridden using the -c option on the <u>submitjob.sh – Submit</u> <u>Batch Threads</u> command line.
Ordinality	Mandatory
Valid Values	Valid thread limit. A value of one (1) is used for single threaded jobs. Default:
Source	Maintained by product templates. Use <u>implementing custom templates</u> to implement a different value.
Applicability	Background Processing
Example	com.splwg.batch.submitter.threadCount=1

A.6.14 com.splwg.batch.submitter.threadNumber - Thread Number

Parameter	com.splwg.batch.submitter.threadNumber
Description	Individual thread number used for execution.
	Note: This setting can be overridden using the -t option on the <u>submitjob.sh – Submit Batch Threads</u> command line.
Ordinality	Mandatory
Valid Values	Valid thread number. The value must be less than or equal to the com.splwg.batch.submitter.threadCount — Thread Limit. A value of zero (0) spawns multiple threads up to the limit expressed in com.splwg.batch.submitter.threadCount — Thread Limit. Default: 0
Source	Maintained by product templates. Use <u>implementing custom templates</u> to implement a different value.
Applicability	Background Processing
Example	com.splwg.batch.submitter.threadNumber=0

A.6.15 com.splwg.batch.submitter.traceProgramEnd - Trace Program End

Parameter	com.splwg.batch.submitter.traceProgramEnd
Description	Enables or disables tracing for the end of the program.
	Note: This setting is designed for developers and for support purposes.
	This setting can be overridden using the -g option on the <u>submitjob.sh – Submit</u> <u>Batch Threads</u> command line.
Ordinality	Mandatory
Valid Values	[true false]
Source	Maintained by product templates for submission.
Applicability	Background Processing
Example	com.splwg.batch.submitter.traceProgramEnd=false

A.6.16 com.splwg.batch.submitter.traceProgramStart - Trace Program Start

Parameter	com.splwg.batch.submitter.traceProgramStart
Description	Enables or disables tracing for the start of the program.
	Note: This setting is designed for developers and for support purposes.
	This setting can be overridden using the -g option on the <u>submitjob.sh – Submit</u> <u>Batch Threads</u> command line.
Ordinality	Mandatory
Valid Values	[true false]
Source	Maintained by product templates for submission.
Applicability	Background Processing
Example	com.splwg.batch.submitter.traceProgramStart=false

A.6.17 com.splwg.batch.submitter.traceSQL - Trace SQL Statements

Parameter	com.splwg.batch.submitter.traceSQL
Description	Enables or disables tracing of ALL SQL statements executed by the program.
	Note: This setting is designed for developers and for support purposes.
	This setting can be overridden using the -g option on the <u>submitjob.sh – Submit</u> <u>Batch Threads</u> command line.
Ordinality	Mandatory
Valid Values	[true false]
Source	Maintained by product templates for submission.
Applicability	Background Processing
Example	com.splwg.batch.submitter.traceSQL=false

A.6.18 com.splwg.batch.submitter.traceStandardOut - Trace Output Statements

Parameter	com.splwg.batch.submitter.traceStandardOut
Description	Enables or disables tracing of ALL in-program debug statements executed by the program.
	Note: This setting is designed for developers and for support purposes.
	This setting can be overridden using the -g option on the <u>submitjob.sh – Submit</u> <u>Batch Threads</u> command line.
Ordinality	Mandatory
Valid Values	[true false]
Source	Maintained by product templates for submission.
Applicability	Background Processing
Example	com.splwg.batch.submitter.traceStandardOut=false

A.6.19 com.splwg.batch.submitter.userId - Security User

Parameter	com.splwg.batch.submitter.userld
Description	User ID used by job to check authorization to underlying application services.
	Note: This setting can be overridden using the -u option on the submitjob.sh — Submit Batch Threads command line.
Ordinality	Mandatory
Valid Values	Valid User ID.
	Note: The SYSUSER account should not be used for non-demonstration environments.
Source	Maintained by product templates. Use <u>Implementing Custom Templates</u> to implement a different value.
Applicability	Background Processing
Example	com.splwg.batch.submitter.userId=USER01

A.6.20 spl.runtime.batch.L2CacheMode - L2 Cache Control

Parameter	spl.runtime.batch.L2CacheMode
Description	Defines the 2nd-level cache mode. Valid values are READ_ONLY (default), READ_WRITE or OFF.
	 READ_ONLY is for performance as it loads the configuration entities into the 2nd-level (JVM-level) cache and accesses them from there itself. In READ_ONLY mode, the cached entities may not be updated.
	 READ_WRITE also loads them into the L2 cache, but they can be updated. The drawback is that an update of a cached entity hits both the database and cache as it gets updated in both places.
	 In OFF mode the 2nd-level cache is completely disabled. Some jobs, for example LDAP import (F1-LDAP), need to update some of these entities (e.g. User), so it requires the L2 cache to be either OFF or READ_WRITE. The choice between OFF and READ_WRITE depends on requirement; the effect is the same.
	Note: This setting can be overridden using the -I2 option on the <u>submitjob.sh</u> – <u>Submit Batch Threads</u> command line.
Ordinality	Mandatory
Valid Values	[READ_ONLY READ_WRITE OFF]
Source	Maintained by product templates for submission.
Applicability	Background Processing
Example	spl.runtime.batch.L2CacheMode=READ_ONLY

A.6.21 tangosol.coherence.distributed.localstorage - Cache Mode

Parameter	tangosol.coherence.distributed.localstorage
Description	Sets whether data is <u>cached</u> local or not. This is used to optimize large networks of submitters and threadpools with cache nodes.
Ordinality	Mandatory
Valid Values	[false true]
Source	Maintained by product templates. Use <u>implementing custom templates</u> to implement a different value.
Applicability	Background Processing
Example	tangosol.coherence.distributed.localstorage=false

A.6.22 tangosol.coherence.role - Submitter Role

Parameter	tangosol.coherence.role
Description	Sets role of Submitter. Informational information on JVM used for monitoring purposes only.
Ordinality	Optional
Valid Values	Generated with the name OUAF_ <batchcode>_Submitter where <batchcode> is the Batch Control identifier for the batch job.</batchcode></batchcode>
Source	Maintained by product templates. Use <u>Implementing Custom Templates</u> to implement a different value.
Applicability	Background Processing
Example	tangosol.coherence.role=OUAF_QABATCH_Submitter

A.7 threadpoolworker.properties (BATCH)

This configuration sets the threadpoolworker configuration for global and individual threadpoolworkers. As with submitters there are global defaults as well as individual threadpoolworker configurations.

Points to Note: Some settings in this file are shared with the <u>submitbatch.properties</u> file but these settings apply to the threadpoolworker JVM's rather than submitter JVM's.

This section is the default set of configuration parameters. Adding Custom JMX Information to Jobs can be done through <u>Implementing Custom Templates</u>.

A.7.1 com.oracle.ouaf.batch.scriptDir - Base Scripts Directory for Infrastructure Job

Parameter	com.oracle.ouaf.batch.scriptDir
Description	The base directory in which the scripts have to be placed for the generic infrastructure job to execute them.
Ordinality	Optional
Valid Values	Directory path.
Source	Defaulted by configureEnv.
Applicability	Background Processing
Example	com.oracle.ouaf.batch.scriptDir=\$SPLEBASE/scripts/generic/batch/expose d/\$OWNER
	\$OWNER would be the owner flag of the batch control thereby allowing restrictions on which scripts might be executed. Additional owners can be provided access by creating symbolic links in those owners' directories.

A.7.2 com.ouaf.batch.disableAutoFlush – Auto Flush Batch L2 Cache

Parameter	com.ouaf.batch.disableAutoFlush
Description	Disables the auto flushing of batch L2 cache. If this value is set to true, the L2 cache auto flush will be disabled.
Ordinality	Mandatory
Valid Values	[true false]. Default value is false.
Source	Generated by template. Use <u>configuring batch using bedit</u> to implement a different value.
Applicability	Business Application Server
Example	com.ouaf.batch.disableAutoFlush=true

A.7.3 com.ouaf.batch.flushIntervalInSeconds – Batch L2 Cache Auto Flush Interval

Parameter	com.ouaf.batch.flushIntervalInSeconds
Description	Sets the time interval between batch L2 cache auto flushes. The time interval should be specified in seconds. Default value is 60.
Ordinality	Optional
Valid Values	Value in seconds. Default is 60.
Source	Generated by template. Use <u>configuring batch using bedit</u> to implement a different value.
Applicability	Business Application Server
Example	com.ouaf.batch.flushIntervalInSeconds=90

A.7.4 com.ouaf.batch.jvmoptions - Threadpool JVM Options

Parameter	com.ouaf.batch.jvmoptions
Description	Custom JVM Options for threadpool.
	Note: This setting can be overridden using the -z option on the threadpoolworker.sh – Manage Threadpools command line.
Ordinality	Mandatory
Valid Values	Valid JVM Options for the Java version used
Source	Maintained by product templates. Use <u>configuring Batch using bedit</u> to implement a different value.
Applicability	Background Processing
Example	com.ouaf.batch.jvmoptions=-Xms1024k -Xmx2048k - XX:MaxPermSize=512m

A.7.5 com.splwg.grid.executionMode - Threadpool Mode of Execution

Parameter	com.splwg.grid.executionMode
Description	Execution Mode used by this threadpool.
	Note: This setting can be overridden using the –e option on the <u>threadpoolworker.sh – Manage Threadpools</u> command line.
Ordinality	Mandatory
Valid Values	[CLUSTERED]
Source	Maintained by product templates.
Applicability	Background Processing
Example	com.splwg.grid.executionMode=CLUSTERED

A.7.6 com.splwg.grid.distThreadPool.threads - Threadpool Thread Limit

Parameter	com.splwg.grid.distThreadPool.threads
Description	Maximum number of threads for a particular threadpool. The format of the setting is: com.splwg.grid.distThreadPool.threads. <poolname>=limit> where: <poolname> is the Name of the threadpool limit> is the thread limit supported by each instance of the threadpool Note: This setting can be overridden using the -p option on the threadpoolworker.sh - Manage Threadpools command line.</poolname></poolname>
Oudinality	
Ordinality	Mandatory
Valid Values	Threadpool names and limit must be valid
Source	Maintained by product templates. Use configuring batch using bedit to implement a different value.
Applicability	Background Processing
Example	com.splwg.grid.distThreadPool.threads.DEFAULT=5

A.7.7 com.splwg.batch.scheduler.daemon - Scheduler Daemon

Parameter	com.splwg.batch.scheduler.daemon
Description	Configures whether the threadpool should execute the online scheduler daemon. The online scheduler daemon checks that the Batch Submission transaction and initiates execution of pending batch jobs.
	Note: This setting can be overridden using the -d option on the <u>threadpoolworker.sh - Manage Threadpools</u> command line.
	This setting should only be set to true in non-Production environment where online submission is enabled.
	In any non-Production environment that uses online submission; one threadpool should have this setting enabled. Typically this is the DEFAULT threadpool but can be any other threadpool.
Ordinality	Mandatory
Valid Values	[true false]
Source	Maintained by product templates. Use <u>Configuring Batch Using Bedit</u> to implement a different value.
Applicability	Background Processing
Example	com.splwg.batch.scheduler.daemon=false

A.7.8 jmx.remote.x.access.file – JMX Access Control

Parameter	jmx.remote.x.access.file
Description	Sets relative location of JMX access control file holding the valid user. Refer to <u>JMX Security</u> for more details.
Ordinality	Mandatory
Valid Values	Relative location of file from \$SPLEBASE/%SPLEBASE%. Defaults to scripts/ouaf.jmx.access.file
Source	Value inherited from templates. Use <u>implementing custom templates</u> to set this value to the desired location and file, if desired.
Applicability	Web Application Server, Business Application Server
Example	jmx.remote.x.access.file=scripts/ouaf.jmx.access.file

A.7.9 jmx.remote.x.password.file – JMX Password Control

Parameter	jmx.remote.x.password.file
Description	Sets relative location of JMX password file holding the valid passwords for jmx.remote.x.access.file. Refer to JMX Security for more details.
Ordinality	Mandatory
Valid Values	Relative location of file from \$SPLEBASE /% \$PLEBASE %. Defaults to scripts/ouaf.jmx.password.file
Source	Value inherited from templates. Use <u>implementing custom templates</u> to set this value to the desired location and file, if desired.
Applicability	Web Application Server, Business Application Server
Example	jmx.remote.x.password.file=scripts/ouaf.jmx.password.file

A.7.10 oracle.ouaf.jmx.remote.maxPortsToTry - Ports to Attempt to Connect to

Parameter	oracle.ouaf.jmx.remote.maxPortsToTry
Description	Number of ports to try starting from either
	oracle.ouaf.jmx.remote.startPort – Override Batch JMX Port or
	spl.runtime.management.rmi.port – JMX Port.
	If <u>oracle.ouaf.jmx.remote.startPort – Override Batch JMX Port</u> is not specified, the property spl.runtime.management.rmi.port is used that as the starting port. If neither property is defined or the maximum number of ports to try has been reached, an exception will be thrown that will prevent the system from starting
Ordinality	Optional
Valid Values	Number. Default: 200
Source	Set by <u>BATCH_RMI_PORT – RMI Port for Batch</u> . Use <u>Configuring Batch Using Bedit</u> to implement a different value.
Applicability	Background Processing
Example	oracle.ouaf.jmx.remote.maxPortsToTry=100

A.7.11 oracle.ouaf.jmx.remote.startPort - Override Batch JMX Port

Parameter	oracle.ouaf.jmx.remote.startPort
Description	Alternative Port number allocated for <u>Batch JMX Reference</u> . This value is typically the same as <u>spl.runtime.management.rmi.port – JMX Port.</u> But may be set to the Coherence JMX port if Coherence based JMX is used on a different port
Ordinality	Optional
Valid Values	Valid JMX Port
Source	Set by <u>BATCH_RMI_PORT – RMI Port for Batch</u> . Use <u>Configuring Batch Using Bedit</u> to implement a different value.
Applicability	Background Processing
Example	oracle.ouaf.jmx.remote.startPort=6510

A.7.12 ouaf.batch.onlineLogDir - Online Line Batch Log Directory

Parameter	ouaf.batch.onlineLogDir
Description	Sets the location of output from online batch submission and batch scheduler integration. If this property is set, batch logs will be accessible via the Batch Run Tree (application UI). Otherwise, the batch logs download link in the application will be disabled.
Ordinality	Optional
Valid Values	Valid location. Defaults to: \$SPLOUTPUT (%SPLOUTPUT% on Windows)
Source	Value inherited from <u>BATCH_ONLINE_LOG_DIR</u> from <u>ENVIRON.INI</u> .
Applicability	Background Processing
Example	ouaf.batch.onlineLogDir=/tmp

A.7.13 ouaf.batch.onlineLogDir.retain – Retain Online Line Batch Log Files

Parameter	ouaf.batch.onlineLogDir.retain
Description	Sets the total number of log files that are to be stored for each batch code and thread number. The log files for the particular batch code and thread number will be deleted except for the latest number of logs specified.
Ordinality	Optional
Valid Values	Number
Source	Generated by template. Use <u>configuring batch using bedit</u> to implement a different value.
Applicability	Background Processing
Example	ouaf.batch.onlineLogDir.retain=3
	The above example will keep the last three logs and delete the rest.

A.7.14 spl.runtime.batch.disableDeferredKeyInserts - Deferred Key Inserts

Parameter	spl.runtime.batch.disableDeferredKeyInserts
Description	Whether the deferring of key insert in batches should be disabled or not.
	Enables (false) or disables (true) deferred Key Inserts.
	The default is to use deferred inserts. However if an aggressive key insert is desired in batches, a value of true should be used.
	Note: This setting is used by particular base batch jobs. Refer to the online documentation for individual batch jobs for more information.
Ordinality	Mandatory
Valid Values	[true false]
Source	Generated by template, Use configuring batch using bedit to implement a different value.
Applicability	Background Processing
Example	spl.runtime.batch.disableDeferredKeyInserts=false

A.7.15 spl.runtime.batch.L2CacheMode - Threadpoolworker L2 Cache Control

Parameter	spl.runtime.batch.L2CacheMode
Description	 Defines the 2nd-level cache mode for threads in threadpool. Valid values are READ_ONLY (default), READ_WRITE or OFF. READ_ONLY is for performance as it loads the configuration entities into the 2nd-level (JVM-level) cache and accesses them from there itself. In READ_ONLY mode, the cached entities may not be updated. READ_WRITE also loads them into the L2 cache, but they can be updated. The drawback is that an update of a cached entity hits both the database and cache as it gets updated in both places. In OFF mode the 2nd-level cache is completely disabled. Some jobs, for example LDAP import (F1-LDAP), need to update some of these entities (e.g. User), so it requires the L2 cache to be either OFF or READ_WRITE. The choice between OFF and READ_WRITE depends on requirement; the effect is the same. Note: This setting can be overridden using the -I2 option on the threadpoolworker.sh - Manage Threadpools command line.
Ordinality	Mandatory
Valid Values	[READ_ONLY READ_WRITE OFF]
Source	Maintained by product templates for threadpoolworker. Use configuring batch using bedit to implement a different value.
Applicability	Background Processing
Example	spl.runtime.batch.L2CacheMode=READ_ONLY

A.7.16 spl.runtime.management.connector.url.default - Batch JMX URL

Parameter	spl.runtime.management.connector.url.default
Description	JMX URL for Batch JMX interface.
	Note: This URL is generated and should not be altered.
Ordinality	Optional
Valid Values	Valid JMX URL
Source	Generated by template.
Applicability	Background Processing
Example	spl.runtime.management.connector.url.default=service:jmx:rmi:///jndi/rmi://{host}:{port}/oracle/ouaf/batchConnector

A.7.17 spl.runtime.management.rmi.port - Batch JMX Port

Parameter	spl.runtime.management.rmi.port
Description	Port number allocated for <u>Batch JMX Reference</u> .
	Note: This setting can be overridden using the —i option on the threadpoolworker.sh — Manage Threadpools command line.
Ordinality	Optional
Valid Values	Valid JMX Port
Source	Set by <u>BATCH_RMI_PORT – RMI Port for Batch</u> . Use <u>Configuring Batch Using Bedit</u> to implement a different value.
Applicability	Background Processing
Example	spl.runtime.management.rmi.port=1001

A.7.18 spl.runtime.options.isDevelopmentMode – Development Mode

Parameter	spl.runtime.options.isDevelopmentMode
Description	 Enables or disables Development Mode for the product. Development mode disables and enables key features within the architecture to allow the Oracle Utilities SDK to be used optimally. The following settings are affected by this parameter: Caching is disabled at all layers of the architecture. This can be renabled manually. Screen Preloading is disabled. This can be renabled manually. Compression is disabled at all layers of the architecture. This can be renabled manually. The product is set to expanded mode to allow developers access to individual JEE objects rather than using WAR/EAR files.
	It is highly recommended that this setting should be set to false in Production environments. This setting is only set to true where the Oracle Utilities SDK is used directly.
Ordinality	Mandatory
Valid Values	[true false]
Source	Derived from WEB_ISDEVELOPMENT parameter from ENVIRON.INI.
Applicability	Web Application Server, Business Application Server, Inbound Web Services
Example	spl.runtime.options.isDevelopmentMode=false

A.7.19 tangosol.coherence.distributed.localstorage - DistributedCache Storage

Parameter	tangosol.coherence.distributed.localstorage
Description	Specifies whether this member of the DistributedCache service enables local storage.
	Note: This setting is used by the Oracle Coherence <u>DistributedCache Service</u> .
Ordinality	Optional
Valid Values	[true false]
Source	Generated by template. Use <u>configuring batch using bedit</u> to implement a different value.
Applicability	Background Processing
Example	tangosol.coherence.localport.adjust=true

A.7.20 tangosol.coherence.distributed.threads - Internal Cache Threads

Parameter	tangosol.coherence.distributed.threads
Description	Specifies the number of daemon threads used by the distributed cache service.
	Note: This setting is used by the Oracle Coherence <u>DistributedCache Service</u> .
Ordinality	Optional
Valid Values	Valid thread numbers. Default: 0
	Note: To improve the batch job performance, we recommend you to set the parameter value to 8 .
Source	Generated by template. Use <u>configuring batch using bedit</u> to implement a different value.
Applicability	Background Processing
Example	tangosol.coherence.distributed.threads=8

A.7.21 tangosol.coherence.invocation.threads - Internal Invocation Threads

Parameter	tangosol.coherence.invocation.threads
Description	Specifies the number of daemon threads to be used by the invocation service. If zero, all relevant tasks are performed on the service thread.
	Note: This setting is used by the Oracle Coherence <u>InvocationService</u> .
Ordinality	Optional
Valid Values	Valid thread numbers. Default: 0
	Note: To improve the batch job performance, we recommend you to set the parameter value to 8 .
Source	Generated by template (wka only). Use <u>configuring batch using bedit</u> to implement a different value.
Applicability	Background Processing
Example	tangosol.coherence.invocation.threads=8

A.7.22 tangosol.coherence.localhost - Unicast Host Address

Parameter	tangosol.coherence.localhost
Description	Host name for local host for Unicast address.
	Note: This setting applies to unicast or <u>well known address</u> implementation. This setting is used by the Oracle Coherence <u>unicast-listener</u> .
Ordinality	Optional
Valid Values	Valid host name defined in hosts file and/or DNS
Source	Generated by template (wka only). Use <u>Configuring Batch Using Bedit</u> to implement a different value.
Applicability	Background Processing
Example	tangosol.coherence.localhost=myserver.example.com

A.7.23 tangosol.coherence.localport - Unicast Port

Parameter	tangosol.coherence.localport
Description	Port number for local host for Unicast address.
	Note: This setting applies to unicast or <u>well known address</u> implementation. This setting is used by the Oracle Coherence <u>unicast-listener</u> .
Ordinality	Optional
Valid Values	Valid port number
Source	Generated by template (wka only). Use <u>Configuring Batch Using Bedit</u> to implement a different value.
Applicability	Background Processing
Example	tangosol.coherence.localport=6570

A.7.24 tangosol.coherence.localport.adjust - Unicast Port Adjustment

Parameter	tangosol.coherence.localport.adjust	
Description	Specifies whether the unicast port is automatically incremented if the specified port cannot be bound to because it is in use.	
	Note:	
	This setting applies to unicast or well known address implementation.	
	This setting is used by the Oracle Coherence <u>unicast-listener</u> .	
Ordinality	Optional	
Valid Values	[true false]	
Source	Generated by template (wka only). Use <u>Configuring Batch Using Bedit</u> to implement a different value.	
Applicability	Background Processing	
Example	tangosol.coherence.localport.adjust=true	

A.7.25 tangosol.coherence.role - Threadpoolworker Role

Parameter	tangosol.coherence.role	
Description	This contains the name of the member role. This name allows an application to organize members into specialized roles, such as cache servers and cache clients. The name is also useful for displaying management information (for example, JMX) and interpreting log entries.	
	Note: This setting is used by the Oracle Coherence member-identity.	
Ordinality	Optional	
Valid Values	Role Name	
Source	Generated by template. Use <u>Configuring Batch Using Bedit</u> to implement a different value.	
Applicability	Background Processing	
Example	tangosol.coherence.role=OUAF_Base_TPW	

A.8 coherence-cache.config.xml

The coherence-cache.config.xml file is generated using the coherence-cache.config.xml.template located in the templates directory.

The <u>format and structure</u> are setup for the implementation of Oracle Coherence for the batch infrastructure within the product.

Note: This file is fixed in format and should not be altered unless instructed by Oracle Support.

A.9 tangosol-coherence-override.xml

The tangosol-coherence-override.xml file is generated using the templates located in the templates directory. There are four templates for this file:

Template	Contents
tangosol-coherence- override.mc.be.template	Multicast Overrides (for <u>Configuring Batch Using Bedit</u>)
tangosol-coherence- override.ss.be.template	Single Server Overrides (for <u>Configuring Batch Using Bedit</u>)
tangosol-coherence- override.wka.be.template	WKA Overrides (for Configuring Batch Using Bedit)
tangosol-coherence- override.xml.template	General Overrides

The <u>format and structure</u> are setup for the implementation of Oracle Coherence for the batch infrastructure within the product.

Note: This file is fixed in format and should not be altered unless instructed by Oracle Support.