Development of Customer Landing Page Oracle FLEXCUBE Universal Banking Release 14.7.2.0.0

Part No. F87755-01

[November] [2023]

FINANCIAL SERVICES

Contents

1	Р	reface.		
	1.1	Audi	ence	3
	1.2	Relat	ted Documents	3
2	С) vervie	w of Customer Landing page Development for Oracle FLEXCUBE	4
	2.1	Radx	ml	4
	2.2	Exter	nsible Development	4
	2.3		gn Steps	
	2	.3.1	Design Process:	5
	2	.3.2	Action	
	2	.3.3	Function Id	6
	2	.3.4	Save Xml Path	7
	2	.3.5	Function Category	8
3	Ν	laster S	Screen	
	3	.1.1	Preferences	9
	3	.1.2	Screens	11
	3	.1.3	Adding a new Tab	13
4	D	Detail	-	15
5	S	umma	ry	17
6	Т	`abs	•	17
7	S	ubsyst	ems	18

1 Preface

This document describes the process of FLEXCUBE Screen Development using Enterprise Limits and Collateral Management Development Workbench.

1.1 Audience

This document is intended for FLEXCUBE Application developers/users that use ODT to develop various FLEXCUBE components.

To Use this manual, you need conceptual and working knowledge of the below:

Proficiency	Resources
FLEXCUBE Functional Architecture	Training programs from Oracle
	Financial Software Services.
FLEXCUBE Technical Architecture	Training programs from Oracle
	Financial Software Services.
FLEXCUBE Object Naming conventions	Development Overview Guide
Working knowledge of Web based	Self Acquired
applications	
Working knowledge of Oracle Database	Oracle Documentations
Working knowledge of PLSQL & SQL	Self Acquired
Language	
Working knowledge of XML files	Self Acquired
Essential knowledge on FLEXCUBE	<u> Development Workbench – Administration</u>
ODT	<u>Development Workbench – Getting Started</u>

1.2 Related Documents

Development of Launch Forms and Others Screens

2 Overview of Customer Landing page Development for Oracle FLEXCUBE

Oracle FLEXCUBE ODT provides the developer with a user friendly console for designing and developing screens for Oracle FLEXCUBE.

ODT assist developers in designing screens with the capability of generating front end scripting files, PL/SQL Packages, Static data scripts, XSDs, Excel templates and html files. This generated code performs validations and does some processing which is common across screens in FLEXCUBE; only the Business logic specific to the screen has to be added by the Developer in back end and front end units.

Example

Release Name: FC 12.1

Release Type: KERNEL, CLUSTER, CUSTOM

ODT will generate all files and developers are supposed to add the business logic in designated units depending on the Release Type.

2.1 Radxml

ODT saves all the activities carried out by the developer in an xml file hereby referred to as **radxml**. Persistence of the screens is achieved through radxml. All the units required for the working of a screen can be generated from its radxml.

If some changes are required on the screen in a future release, the same radxml can be loaded and changes can be done on this radxml. ODT can segregate the changes done on different releases and saves the radxml accordingly.

Radxml will adhere to following naming convention

Function Id name + _RAD.xml

Example: STDCULND_RAD

2.2 Extensible Development

In extensible framework, any development on FLEXCUBE is classified as on any of the following stage (also referred to as release type)

i) KERNEL

This refers to the core product.

Example: FC 12.1

ii) CLUSTER

This refers to any region specific enhancements /developments done on top of the kernel product. The changes done in a cluster pack will be non invasive to the kernel product. *Example:* FC 12.1 *India cluster*

iii) CUSTOM

Any enhancements required by the customer/bank are done on this level. It will be non invasive of the changes done in kernel and cluster packs *Example: Customizations for MODEL bank on FC 12.1 India cluster*

ODT can segregate the changes done on different releases and saves the radxml accordingly. It generates the files depending on the release type and developers can add the business logic to the release type specific files. Thus the code remains non invasive of the existing code.

2.3 Design Steps

Sequence of Steps to be followed while developing a screen in ODT is:

- 1. Identifying the data sources and their relations
- 2. Logically grouping the data sources into Data Blocks
- 3. Designing Screen Layout
- 4. Logically grouping the Block Fields into Field sets
- 5. Attaching Call forms and launch forms if any
- 6. Defining LOVs
- 7. Designing Summary
- 8. Defining Actions

Refer respective sections for detailed explanation of each step

Saving Radxml

While Development, save radxml at constant intervals. Click on save icon in the top right for having the work. Radxml would be saved in the user directory maintained

2.3.1 Design Process:

Click on Customer Landing Page node in the browser tree found in the Landing page of ODT. Customer Landing Page window gets launched.



Oracle FLEXCUBE ODT Landing Page

While creating a new function in customer landing page in ODT, below information needs to be provided in the Header section

The Header portion of the Customer Landing Page screens consists of the following fields:

2.3.2 Action

New and Load options are provided for this field.

For a new screen development, select the action as New; if an existing screen radxml has to be loaded for customization select Load option

If the action is load then corresponding radxml has to be loaded using browser option in Save Xml Path; all the header information will get populated.

2.3.3 Function Id


If the Action is selected as New, the function Id name needs to be specified. Function Id is the unique name with which a screen is identified.

Function Id name should follow the FLEXCUBE standard naming convention.

- Function Id name to have maximum length of 8 characters
- For detail screens the third character should be 'D'
- For report screens the third character should be 'R'
- For call form function ids the third character should be 'C'
- First 2 characters should specify the module name for which the particular function id is used (recommended).

2.3.4 Save Xml Path

The label description of the field will change depending on the action .If the action is load, ODT attaches a Browse button to it so that user can browse the radxml and load it.



ORACLE: FLEXCUBE Development Workbench for Universal Banking			Р	prasanti	h
Browser -		Windows	Options	Sign Out	
Customer Landing Page				-	
		l	X =	77 🧃	4
Action New V Function Id STDMA	Function Category Master Save XML Path Ubtail Tabs Subsystem				

2.3.5 Function Category

These are the categories of Radxml Master, Detail, Summary, Tabs and Subsystems.

3 Master Screen

ORACLE FLEXCUBE Developm	ent Workbench for Universal Banking				F	pras	anth
Browser -				Windo	ws Options	Sign	Out
Customer Landing Page							_ ×
					📔 🗶 🗉	V	🧐 🔿
Action New V Function Id STDMA			Function Category Master]			
Search	Preferences						¥ 🗸
Construction of the second sec	 ✓ Head Office Fun ✓ Logging Require ✓ Authorizati ✓ Tank Modificatio ✓ Field Log Require ✓ Mutti Branch Act ☐ Excel Export Re 	ed on ns red cess	Module Module Description Branch Program Id Process Code SVN Repository URL Transaction Block Name Transaction Field Name		<u> </u>		
					Control String		
	Function Id		Module *	Module Des	scription		~
	STDMA	ST		Static Maintenance			
							~

3.1.1 Preferences

Function id level preferences like module, logging required, tanking modification Main menu, Sub-Menu1, Sub-Menu2 is maintained through Preferences screen in ODT.

The data maintained in Preferences Screen will be used for generating static data script for tables SMTB_MENU, SMTB_FUNCTION_DESCRIPTION, SMTB_ROLE_DETAIL and SMTB_FCC_FCJ_MAPPING

• Module

It captures the Module of the function id. Developer can choose module name from the list of values provided. List of values is populated based on the modules maintained in SMTB_MODULE table of the business schema (current FLEXCUBE environment to which tool is mapped).

Module Code has to be provided mandatorily. Module name provided would be reflected in the script for SMTB_MENU generated by ODT (in module column). This will also be considered while naming the packages generated by the tool. First two characters of the packages generated will be taken from the module code maintained.

• Module Description

Module description gets defaulted based on the module code selected.

• Head office Function

It captures whether the function is a head office function or not. It will be reflected in the static script for SMTB_MENU in column HO_FUNCTION.

If the function is a head office function, only query operation will be possible at all the other branches for the particular screen.

• Logging Required

It captures whether logging is required for the function or not. This will also be reflected in script generated for SMTB_MENU (column LOGGING_REQD).

If this option is selected, all the request and response for the functionId will be logged in CSTB_MSG_LOG. This is used for View Change option.

Auto Authorization

It captures whether Auto Authorization is allowed for the function or not. This will also be reflected in script generated for SMTB_MENU (column AUTO_AUTH).

Note that auto authorization is possible only if it is allowed at function id level, user level and the branch level.

• Tank Modification

It captures whether modification to be tanked for the function or not. This will be reflected in TANK_MODIFICATIONS column of SMTB_MENU table script.

If tank modification is enabled, then the record in that screen would be logged to logging tables and taken up for processing (*untanking*) in later stage during EOD operations. Currently this is applicable only for maintenance screens.

• Field Log Required

It captures whether field Logging is required for the function or not. This will be reflected in the FIELD_LOG_REQD column in SMTB_MENU.

If field log required is enabled, then all operations on the screen will be logged to logging tables (STTB_FIELD_LOG.STTB_RECORD_LOG etc). Currently this is applicable only for maintenance screens.

• Excel Export Required

This field captures whether option to export records from summary screen to excel is required

• Multi Branch Access

It captures whether multi branch access is required for the function Id or not. This will be reflected in MULTIBRANCH_ACCESS column of SMTB_MENU table script generated.

If multi branch access is allowed, then records of different branches for the screen can be modified from a single branch.

• Txn Block Name

It captures the transaction Block Name. This is applicable only if multi branch access is allowed for the screen. Select the block from the select list which contains the field for branch code

Txn Field Name

•

It captures the transaction Field Name. This is applicable only if multi branch access is allowed for the screen. Select list provides all the block fields for the transaction block selected. Choose the field for branch code from the list.

Txn Block Name and Txn Field Name will be reflected in the system JavaScript file (SYS js) generated by ODT. Developer has to code for querying the records based on the branch code value of this field.

• Branch Program ID

It captures branch program id for the function.

Process Code

This can be used to map which process needs to be initiated during screen launch. This is used for workflow screens.

• SVN Repository Url

This is applicable only if integration to SVN (version control tool) is required. Path of the SVN repository till the module needs to be provided in this field.

In the multiple entry block , developer needs to maintain all the related function Id names for the screen. ODT will default the name of the function Id to the first row of the multiple entry along with the module maintained earlier.

If any other function id is required for the particular screen, developer has to add the row.

Example: For FTDTRONL screen, developer designs a detail screen. He also wants to add one summary screen to the screen as well as gateway function Id for web services.

For this, he can add two new columns FTSTRONL (for summary) and FTGTRONL (for gateway operations) to the block as shown below.

3.1.2 Screens

- Right click on screens and add.
- Give the name as CVS_Master.
- Press OK.

Browser		lopment Workbench for Universal Banking	Windows	P prasanth Options Sign Out
Customer La				
				 X = 7 9 \$
	Action New V Function Id STDMA		Function Category Master V Slave XML Path D/RadXML	
Search		Add Screen	×	4
Preferen	ices	Screen Name CVS_Master ×		
		Ok Cancel	Main Scn	100

The Following UI will appear.

Action New V Function Id STDMA	Screen Details Screen Name CVS_M			Function Category Master Save XML Path DESTINATIC		Windows	Options	Sign Out – 7 🧐
Action New V Function Id STDMA							X	
Function Id STDMA							X I	77 🧐
Function Id STDMA								
Function Id STDMA								
Preferences				Save XIVIL Patri DESTINATIO	IN .			
Preferences								
Screens	CVS M						- (x 🖸 🛒
		ASTER		Main Screen				
	Screen Title		×=	OBIEE				
	Screen Size Small		~	✓ Visible				
🗉 🚞 HEADER			×	Query Required				
🗉 🧰 BODY	Exit Button Type Default	ounool						
🗉 🚞 FOOTER								
								+ -
	Argument Name	Source Block	Source Field	Argument Value	Target Block	Target Field	Active	~
								\sim

3.1.3 Adding a new Tab

- Right click on body and add.
- Give the tab name as Tab_1.
- In the Tab Details give map the function name in the function name field.
- Here it is STDDE.
- In the Tab type choose whatever you want to map here I am mapping Details.

ORACLE' FLEXCUBE Developm	nent Workbench for Universal Banking			P pra	santi	h
Browser 🗸		Windows	Option	s Siç	jn Out	
Customer Landing Page						. ×
		E	×	= 7	9	⇒
Action New 🗸	Function Category Master					
Function Id STDMA	Save XML Path DESTINATION					
Search	Body				4	~
Preferences CVS_MASTER → CVS_MASTER → HEADER → HEADER → RAdd → RAdd						

Browser	E FLEXCU	BE Developn	nent Workbench	for Universal Ba	nking				Windows	P pra	asanth _{gn Out}
Customer L	Landing Page									× = 7	×
	Action Function Ic						ction Category Ma ave XML Palh DES				-
Search			Add Tab					×			4
Prefer	ences ns		Tab Na	me TAB_1		×					
	S_MASTER HEADER				Ok Canc	el					

ORACLE FLEXCUBE Developm	ent Workbench for Universal Banking		P prasanth
Browser 🗸			Windows Options Sign Out
Customer Landing Page			- ×
			🖫 🗷 🗏 🐬 🧐 🔶
Action New V Function Id STDMA		Function Category Master	
Search	Tab Details		Dependent Fields 🚽 = 🗵 🗳 🦯
 Preferences Screens CVS_MASTER HEADER BODY TAB_MAIN TAB_1 FOOTER 	Screen Name Tab Name Tab Label Function Name Tab Type Detail	Visible	

Generating Radxml and other Artifacts.

		Jniversal Banking			F	^o prasan
owser 🗸					Windows Options	Sign Out
tomer Landing Page						
					🛛 🗶	3 🖗 🌒
ierate						
Front-End Files	System Packages	Hook Packages		Meta Data	Others	^
RadXML	Main Package Spec	Kernel Package Spec	Menu Details	✓ Label Details	✓ Xsds	
Screen Xml	Main Package Body	Kernel Package Body	Datasource Details	Block PK Columns	Xsd With Annotations	
System JS	Notification Triggers	Cluster Package Spec	✓ LOV Details	Function Call Forms	Screen Html	
	Upload Package Spec	Cluster Package Body	Block Details	Gateway Details	Upload Table Trigger	
	Upload Package Body	Custom Package Spec	Screen Details	Notification Details	Upload Tables Definition	
		Custom Package Body	Amendable Details	 Function Parameters 	Archive Table Definition	
			Call form Details	Purge Details		
			Summary Details			~
SI.No		File Name	File	Туре	Status	
						~
						~
					Ok	Exit
					Ok	Exit
					Ok	Exit
					Ok	Exit
					Ok	Exit
					Ok	Exit

4 Detail

Function category as Detail

	ent Workbench for Universal Banking			pras	
Browser -		Windows	Options	Sign	Out
Customer Landing Page		•		77	-
	Master	E	× =	17	9
Action New V Function Id STDDE	Function Cereory Detail				
Search					
 Preferences DataSource DataBlocks Screens FieldSets LaunchForms Summary 					

Module as ST in Preferences Screen

ORACLE FLEXCUBE Developm	ent Workbench for Universal Banking		P prasanth
Browser -			Windows Options Sign Out
Customer Landing Page			_ >
			🔚 🗵 🗏 🐬 🤤 🔿
Action New Function Id STDDE		Function Category Detail V Save XML Path DESTINATION	L
Search	Preferences		Ш,
Preferences DataSource DataSource Screens Screens Screens LauchForms Summary	Head Office Fur Logging Require Table Auto Authorizat Tank Modificatic Field Log Requi Kulti Branch Ac Excel Export Re	Inclusion Inclusion of Module Description on Branch Program Id ns Process Code ced Process Code cess SVN Repository URL	ST P3 Static Maintenance Choose Block V Choose Field V
			Control String 🛨 🗖
	Function Id STDDE	Module *	Module Description

ORACLE FLEXCUBE Developm	nent Workbench for Universal Banking	P prasanth
Browser -		Windows Options Sign Out
Customer Landing Page		-
		🔚 🗵 🗐 🚱 🤤
Action New V Function Id STDDE		Category Detail V ML Path DESTINATION
 Preferences DataSource CSTBS_CONTRACT_EVENT_LOC DataBilocks Delete FieldSets LaunchForms Summary 	Data Source CSTBS_CONTRACT_EVENT_LOG Master Yes Relation Type One To One Multi Record No PK Cots CONTRACT_REF_NO-EVENT_SEQ_NO PK Types * CONTRACT_REF_NO-EVENT_SEQ_NO PK Types * VARCHAR2-NUMBER Upload Table Upload Where Clause	Parent Relation Where Clause Default Order By Type Normal Mandatory

Adding Tables and other information. Detail screen in customer Landing page is similar to developing others Screen. For reference please follow doc.

Development of Launch Forms and Others Screens

5 Summary

Summary screen in Customer Landing Page is similar to Summary screen in normal Function Generation.

Please follow doc as <u>Oracle FLEXCUBE Enterprise Limits and Collateral Management ODT Screen</u> <u>Development</u>

6 Tabs

Tabs screen is part of master screen, tabs screen contains group of screens in it.

Each screen is details under each tab.

Customer Landing Page			_ ×
			🔚 🗙 🗐 7 🥞 🤿
Action Load Function Id STDCUTAB Search	Tab Details	Function Category Tabs	Dependent Fields 🔶 🗕 🔊 🍃
Preferences DataSource DataBlocks Screens CVS_MAIN DataBlocks CVS_MAIN DEADER DODY TAB_SAVINGS TAB_SAVINGS TAB_RD TAB_COANS TAB_FX DEPOSITS TAB_FX FieldSets LaunchForms Summary	Screen Name CVS_MAIN Tab Name TAB_SAVINGS Tab Label LBL_CASAACC Function Name STDCUDEM Tab Type Detail	Visible	

7 Subsystems

Customer Landing Page					_ ×
					🖫 🗶 🗐 7 🧃 🔿
Action Load V Function Id STDCUNEW	Block Field Properties		gory Subsystem V Path STDCUNEW_F BF	ROWSE	- K Q 9
Preferences DataBlocks BLK_MSTER BTN_EC_DEPOSIT BTN_EC_DEPOSIT BTN_TO BTN_TO BTN_SI BTN_SI BTN_SI BTN_SI BTN_CONV BTN_FX CVS_MAIN LaunchForms	Field Name • BTN_CASA_ACCNT Field Label LBL_CASA_ACCNT DataSource Column Name • Data Type • Display Type Item Type Control • Parent Field • Related Block Related Field • LOV Name Off Line LOV Name Fieldset Name	Maximum Le Minimum V Maximum V Maximum Decir TextArea R TextArea Colu Default V Preview V	size		Required Visible Read Only Calender Text Popup Edit Required Uppercase Only LOV Validation Required Input by LOV Only Not Required In Xsd Report Parameter Format Required Hot Key Required Focus Required Exact Fetch
	Custom Attributes Events Event Name Function N Onclick	ame Event Type Launch Form V	Button Screen	CallForm Name	Screen Name

This category is used to display subsystem buttons to launch screens.



Development of Customer Landing Page [November] [2023] Version 14.7.2.0.0

Oracle Financial Services Software Limited Oracle Park Off Western Express Highway Goregaon (East) Mumbai, Maharashtra 400 063 India

Worldwide Inquiries: Phone: +91 22 6718 3000 Fax:+91 22 6718 3001 www.oracle.com/financialservices/

Copyright © 2007, 2023, Oracle and/or its affiliates. All rights reserved.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate failsafe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

This software or hardware and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.