

Java Accounting Installation
Oracle FLEXCUBE Universal Banking
Release 14.7.4.0.0
Part No. F98075-01
[June] [2024]



Table of Contents

- 1. **JAVA ACCOUNTING INSTALLATION** 1-1
 - 1.1 INTRODUCTION 1-1
 - 1.2 PREREQUISITES 1-1
 - 1.3 SERVER SETUP 1-1
 - 1.3.1 INFRA Services 1-1
 - 1.3.2 Linux Server Setup 1-2
 - 1.3.3 Windows Server Setup..... 1-2
 - 1.4 WAR DEPLOYMENT AFTER BUILD 1-3
 - 1.5 ORDER OF SERVER START..... 1-3
 - 1.6 OBAC MAINTENANCE IN FCUBS 1-5

1. Java Accounting Installation

1.1 Introduction

This document provides steps to configure Application Server for JAVA Accounting Integration with Oracle FLEXCUBE Universal Banking.

1.2 Prerequisites

Java Accounting installation requires a Weblogic domain.

NOTE: In the following sections, 10.10.10.10 IP address and 1010 port are used as an example. Use valid IP and Port of corresponding server.

1.3 Server Setup

Java AC Setup includes two sets of services:

- INFRA Services
- JAVA AC Services

This section contains following subsections:

- [1.3.1 INFRA Services](#)
- [1.3.2 Java AC Services](#)
- [1.3.3 Linux Server Setup](#)
- [1.3.4 Windows Server Setup](#)

1.3.1 INFRA Services

There are two services under this category.

- **Discovery Service:** This service is required for Java AC Services Registration. On start-up all Java AC services will be registered with Discovery Service. The registered services can make inter-service calls by making use of Discovery Service.

Service Name: *plato-discovery-services-5.0.0.war*

- **Config Service:** All the configuration related details will be stored in a database table (table name: PROPERTIES). Config service provides the required configuration details for the corresponding Java AC Services during service start up.

Service Name: *plato-config-services-5.0.0.war*

1.3.2 Java AC Services

This includes ECA and Accounting service INFRA services, and Java AC Services must be deployed on two separate Managed Servers (Any name can be given to Managed Servers).

1. **ConfigServer:** In this managed server, INFRA Services should be deployed (*plato-discovery-services-5.0.0.war* and *plato-config-services-5.0.0.war*).
2. **JavaACServer:** In this managed server, all the Java AC services should be deployed.

Following Data Sources have to be created for INFRA and Java AC Services:

Data Source JNDI Name	Type	Targets
jdbc/OBAC	Non-XA Datasource	JavaACServer
jdbc/PLATO	Non-XA Datasource	JavaACServer, ConfigServer
jdbc/PLATOBATCH	Non-XA Datasource	JavaACServer

1.3.3 Linux Server Setup

Include the following lines in *setDomainEnv.cmd* or *setDomainEnv.sh* of the Weblogic domain:

```
JAVA_OPTIONS="{JAVA_OPTIONS} {JAVA_PROPERTIES} -Dflyway.enabled=false -  
Dspring.flyway.enabled=false -Dplato.services.config.uri=http://<config-server-ip>:<config-  
server-port> -Dplato.service.logging.path=<Debug Path where Logs are to be written>" -  
Dserver.id=<server id> - Dspring.cloud.loadbalancer.ribbon.enabled=false  
export JAVA_OPTIONS
```

For example,

```
JAVA_OPTIONS="{JAVA_OPTIONS} {JAVA_PROPERTIES} -Dflyway.enabled=false -  
Dspring.flyway.enabled=false -Dplato.services.config.uri=http://10.10.10.10:1010 -  
Dplato.service.logging.path=/mnt/FC144/ACLogs" -Dserver.id=1 -  
Dspring.cloud.loadbalancer.ribbon.enabled=false
```

```
export JAVA_OPTIONS
```

1.3.4 Windows Server Setup

Include the following line in *setDomainEnv.cmd* or *setDomainEnv.sh* of the Weblogic domain:

```
set JAVA_OPTIONS=%JAVA_OPTIONS% %JAVA_PROPERTIES% -  
Dplato.services.config.uri=http://<config-server-ip>:<config-server-port> -Dflyway.enabled=false -  
Dspring.flyway.enabled=false -Dplato.service.logging.path=<Debug Path where Logs are to be  
written> -Dserver.id=<server id> - Dspring.cloud.loadbalancer.ribbon.enabled=false
```

For example,

```
set JAVA_OPTIONS=%JAVA_OPTIONS% %JAVA_PROPERTIES% -Dflyway.enabled=false -  
Dspring.flyway.enabled=false -Dplato.services.config.uri=http://10.10.10.10:1010 -  
Dplato.service.logging.path=D:/ACLogs -Dserver.id=1 -  
Dspring.cloud.loadbalancer.ribbon.enabled=false
```

Server Id parameter should be a number used to uniquely identify an application instance. If only one deployment of a service is present, this value has to be set to 1. In case of multiple deployments, number needs to be changed from 1 to the number of instances can be assigned to the server, where deployment is done.

Alternatively, if the parameters need to be set specific to a Managed Server, where Services are deployed, then these properties can be set in **Servers > Managed Server > Server Start** in the argument section.

NOTE: It will be useful only if Node-Manager is used to start managed servers.

Java Home:	<input type="text"/>	The Java home directory (path on the machine running Node Manager) to use when starting this server. More Info...
Java Vendor:	<input type="text"/>	The Java Vendor value to use when starting this server. More Info...
BEA Home:	<input type="text"/>	The BEA home directory (path on the machine running Node Manager) to use when starting this server. More Info...
Root Directory:	<input type="text"/>	The directory that this server uses as its root directory. This directory must be on the computer that hosts Node Manager. If you do not specify a Root Directory value, the domain directory is used by default. More Info...
Class Path:	<input type="text"/>	The classpath (path on the machine running Node Manager) to use when starting this server. More Info...
Arguments:	<pre>-Dflyway.enabled=false -Dspring.flyway.enabled=false - Dplato.services.config.uri=http://10.10.10.10:1010 - Dplato.service.logging.path=D:/ACLogs -Dserver.id=1</pre>	The arguments to use when starting this server. More Info...

1.4 WAR Deployment after Build

As part of FCUBS EAR build, in addition to FCUBS EAR, Java AC wars and INFRA wars will get copied into the destination location.


Below are the locations where the wars will be copied after build:

1. **FCUBS Application EAR and All Adapter EARs:** Available in the destination folder.
2. **INFRA Service WARs:** *plato-discovery-services* war and *plato-config-services* war will be available in the destination folder.

Deploy all the INFRA Service WARs in **ConfigServer**.

3. **Java AC Service WARs:** All the Java AC Service WARs will be copied in “AC” folder under the destination folder.

Deploy all the Java AC Service WARs are in **JavaACServer**.



1.5 Order of Server Start

After deployment or server restart, services have to be started in following sequence:

- a. plato-config-service
- b. plato-discovery-service
- c. Java AC Services

When servers are restarted, ensure to start **ConfigServer** first and then **JavaACServer**. On every restart of **ConfigServer**, *plato-discovery-service* must be stopped and started. This is required as Discovery requires properties entries for self-registration to be picked from *plato-config-service*. In order to check if all the services have started, below discovery URL can be checked:

<http://<config-server-ip>:<config-server-port>/plato-discovery-service>

For example,

<http://10.10.10.10:1010/plato-discovery-service>

NOTE: All the deployed Java AC Services should get listed in the service discovery URL.

1.6 OBAC Maintenance in FCUBS

Below maintenances are required in FCUBS:

1. Properties Maintenance (CSDPROPM):

- a. Launch the screen and query for entry present in LOV for Reference Number:

The screenshot shows the 'Amend Service Properties' window. At the top, there is a search bar with the text 'Enter Query'. Below it are three input fields: 'Reference Number', 'Service URL', and 'Service Port'. To the right of these fields are two radio buttons labeled 'Level', with 'Service' selected. Below the input fields are two data tables. The first table is titled 'Service Name' and has columns for 'Service Name' and 'Service Description'. The second table is titled 'Service Details' and has columns for 'Primary Key' and 'Value'. Both tables show 'No data to display.' and pagination controls indicating 'Page 1 (0 of 0 items)'. At the bottom right, there are 'Audit' and 'Exit' buttons.

Note: For the Primary key **obac.account.lock.timeout**, the value should be given in milliseconds for the 14X version and it should be seconds for 12X versions by default.

- b. Unlock the screen, Select All for **Update Service Details**, and update the Service URL and Service Port to as below:

Service URL: <http://<config-server-ip>:<config-server-port>/plato-discovery-service/eureka>

Service Port: JavaACServer Managed Server Port

2. External Source Preferences (ACDPARAM):

Accounting Parameters

Unlock

Deferred Job Parameters

Parameter	Param Value
AC_EA_PURGE_COMMIT_FREQ	500
AC_EA_PURGE_RET_DAYS	2
HANDOFF_FETCH	5000

Page 1 of 1 (1-14 of 14 items) | < 1 >

External Source Preferences

Source Code	Auto Generate Reference Number	Process Code
.	<input type="checkbox"/>	ZEXA

Page 1 of 1 (1 of 1 items) | < 1 >

External Statement Preferences

Statement Reference Number Transaction Reference Number

Change Log Audit Exit

If the Transaction reference no has to be generated by DDA system corresponding details has to be maintained using ACDPARAM.



Java Accounting Installation
[June] [2024]
Version 14.7.4.0.0

Oracle Financial Services Software Limited
Oracle Park
Off Western Express Highway
Goregaon (East)
Mumbai, Maharashtra 400 063
India

Worldwide Inquiries:

Phone: +91 22 6718 3000

Fax: +91 22 6718 3001

<https://www.oracle.com/industries/financial-services/index.html>

Copyright © 2007, 2024, Oracle and/or its affiliates. All rights reserved.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate failsafe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

This software or hardware and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.