

Oracle® Communications Convergent Charging Controller Advanced Control Services Alarms Guide



Release 15.0.0

October 2023

The Oracle logo, consisting of the word "ORACLE" in white, uppercase, sans-serif font, centered within a solid red square.

Copyright

Copyright © 2023, Oracle and/or its affiliates.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs (including any operating system, integrated software, any programs embedded, installed or activated on delivered hardware, and modifications of such programs) and Oracle computer documentation or other Oracle data delivered to or accessed by U.S. Government end users are "commercial computer software" or "commercial computer software documentation" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, reproduction, duplication, release, display, disclosure, modification, preparation of derivative works, and/or adaptation of i) Oracle programs (including any operating system, integrated software, any programs embedded, installed or activated on delivered hardware, and modifications of such programs), ii) Oracle computer documentation and/or iii) other Oracle data, is subject to the rights and limitations specified in the license contained in the applicable contract. The terms governing the U.S. Government's use of Oracle cloud services are defined by the applicable contract for such services. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle, Java, and MySQL are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Inside are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Epyc, and the AMD logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

Contents

Alarm Topic Description1

Advanced Control Services Alarms.....3

Alarm Topic Description

Alarm Generation

Alarms on each configured node are written to the syslog and are then captured by the smsAlarmDaemon for entry in the SMF database.

For management of these alarms, see *Service Management System Technical Guide*.

Severity Levels

This table describes the alarm severity levels.

Level	Abbreviation	Description
Critical	C	These alarms are raised when the application has encountered an error indicating that the system is unable to function.
Error	E	These alarms indicate the application has encountered a serious problem completing a necessary task and could not complete the task.
Warning	W	Warnings are raised to indicate the application encountered a problem completing a non-mission critical task.
Notice	N	Notices are raised to indicate that the application has completed a task successfully.

Alarm Format

Alarms usually follow this format:

```
Mon DD 24:MM:SS hostname process name: [ID alarmID user.severity] process(PID)
SEVERITY: Alarm text with possible variables
```

Where:

Variable	Description
Mon DD	Month and date the alarm was logged.
24:MM:SS	Time the alarm was logged in 24 hour format.
hostname	Name of the machine on which the alarm was generated.
process name	Name of the process which logged the alarm.
alarmID	ID number of the alarm.
severity	Alarm severity.
process	Name of the process which logged the alarm.
PID	Process ID of the process which logged the alarm.
SEVERITY	Alarm severity.
Alarm text	Alarm text. This may include variables such as node number. Note: In some cases, the entire alarm text is generated from variables.

Note: Some alarms from some subsystems may have a different format.

Example: This text shows an smsMaster alarm about pending update queues.

```
Mar 30 13:34:54 prodsmpl smsMaster: [ID 953149 user.warning] smsMaster(17833)
WARNING: Pending queue now above 15 (Worst Node 317)
```

Alarm Text and Variables

The %d and %s symbols represent variables within the alarm text. These values are generated by the subsystem and added to the message when the alarm is raised.

Usually the %d is a number and the %s is text in the context of the message to complete the alarm message. Occasionally other % symbols are also used (for example, %u) for different variables.

Further Information

For more information about:

- The SMS Alarms subsystem, see *Service Management System Technical Guide*
- Creating and maintaining the SMS Alarm Relay rule set, see *Service Management System User's Guide*

Advanced Control Services Alarms

Alarm	Severity	Text	Cause	Resolution	Service
11196	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR: Could not load ACS Compiler Plugin %s %d	A compiler daemon plugin, as specified by a CompilerPlugin line in acs.conf on the SMP, cannot be loaded	Make sure that the specified file exists somewhere in the shared library path of acs_oper and is readable.	ACS
11197	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR: Could not find symbol sharedLibraryInit in ACS Compiler Plugin %s %d	The compiler plugin shared library soes not contain a required function.	Contact support.	ACS
11198	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR: ACS Compiler Plugin %s %d returned FALSE from sharedLibraryInit	A compiler daemon plugin, as specified by a CompilerPlugin line in acs.conf on the SMP, cannot be initialised.	Contact support.	ACS
11199	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR: Could not find symbol compilerPlugin in ACS Compiler Plugin	The compiler plugin shared library soes not contain a required function.	Contact support.	ACS
11200	WARNING	acsSnCpActAlarms(%d) WARNING: Scheduled Control Plan(%s %d) for Customer(%s %d), Service Number(%d) has been temporary disabled by Alternative Control Plan Activation	Alternative Control Plan Activation has temporarily disabled scheduled control plans	Find out the reason why Alternative Control Plans have been activated for this ACS Customer. If appropriate, deactivate Alternative Control Plans	ACS
11201	CRITICAL	acsSnCpActAlarms(%d) CRITICAL: Error connecting to Oracle database.	Process cannot log into Oracle Database	Check Oracle User ID and Password. Check database status	ACS

Alarm	Severity	Text	Cause	Resolution	Service
11202	ERROR	DEF123slee_acs: slee_acs(%d) ERROR: Unexpected empty TCAP_END received	An invalid TCAP_END message was received.	This is a protocol error on the network side. An empty TCAP_END should not be sent to the SCP in response to an InitiateCallAttempt message.	ACS
110000	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR DB Reconnect on Restart=%d acsCompilerDaemon.cc@%d: Unable to connect to Oracle	Cannot connect to ORACLE.	Refer to ORACLE/application expert first (Check the following). 1) Verify that ORACLE is running through checking the status of the listener(lsnrctl) and restart ORACLE only if necessary. 2) Check the environment variables and/or configuration files: ORACLE_SID(environment), tnsnames.ora(configuration file), listener.ora(configuration file). Verify that the username and password for the current machine is correct. 3) Observe startup output for errors. Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110001	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR main=%d acsCompilerDaemon.cc@%d: Unable to connect to Oracle	Cannot connect to ORACLE.	Refer to ORACLE/application expert first (Check the following). 1) Verify that ORACLE is running through checking the status of the listener(lsnrctl) and restart ORACLE only if neccessary. 2) Check the environment variables and/or configuration files: ORACLE_SID(environment), tnsnames.ora(configuration file), listener.ora(configuration file). Verify that the username and password for the current machine is correct. 3) Observe startup output for errors. Finally contact support.	ACS
110002	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR updateCompiledCallPlanData=%d acsCompilerDBConnection.pcc@%d: Compiled Structure too large, Max 65536 bytes	ORACLE error - error selecting from the ACS control plan compiled list.	Refer to ORACLE/application expert first (Check the following). 1) Verify that ORACLE is running through checking the status of the listener(lsnrctl) and restart ORACLE only if neccessary. 2) Check the environment variables and/or configuration files: ORACLE_SID(environment), tnsnames.ora(configuration file), listener.ora(configuration file). Verify that the username and password for the current machine is correct. 3) Observe startup output for errors. Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110003	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR compileCallPlans=%d acsCompilerDaemonDB.pcc@%d: Data in ACS_COMPILE_LIST is invalid	ORACLE error - error selecting from the ACS control plan compiled list.	Refer to ORACLE/application expert first (Check the following). 1) Verify that ORACLE is running through checking the status of the listener(lsnrctl) and restart ORACLE only if neccessary. 2) Check the environment variables and/or configuration files: ORACLE_SID(environment), tnsnames.ora(configuration file), listener.ora(configuration file). Verify that the username and password for the current machine is correct. 3) Observe startup output for errors. Finally contact support.	ACS
110004	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR compileCallPlans=%d acsCompilerDaemonDB.pcc@%d: Invalid data was selected from the database	ORACLE error - error selecting from the ACS control plan compiled list.	Refer to ORACLE/application expert first (Check the following). 1) Verify that ORACLE is running through checking the status of the listener(lsnrctl) and restart ORACLE only if neccessary. 2) Check the environment variables and/or configuration files: ORACLE_SID(environment), tnsnames.ora(configuration file), listener.ora(configuration file). Verify that the username and password for the current machine is correct. 3) Observe startup output for errors. Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110005	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR findCPDID=%d acsCompilerDBConnection.pcc@%d: Data selected from Oracle was shortened	ORACLE error - error selecting from the ACS control plan compiled list.	Refer to ORACLE/application expert first (Check the following). 1) Verify that ORACLE is running through checking the status of the listener(lsnrctl) and restart ORACLE only if neccessary. 2) Check the environment variables and/or configuration files: ORACLE_SID(environment), tnsnames.ora(configuration file), listener.ora(configuration file). Verify that the username and password for the current machine is correct. 3) Observe startup output for errors. Finally contact support.	ACS
110006	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR findStructure=%d acsCompilerDBConnection.pcc@%d: Data selected from Oracle was shortened	ORACLE error - error selecting from the ACS control plan compiled list.	Refer to ORACLE/application expert first (Check the following). 1) Verify that ORACLE is running through checking the status of the listener(lsnrctl) and restart ORACLE only if neccessary. 2) Check the environment variables and/or configuration files: ORACLE_SID(environment), tnsnames.ora(configuration file), listener.ora(configuration file). Verify that the username and password for the current machine is correct. 3) Observe startup output for errors. Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110007	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR getAnnouncementInformationString =%d acsCompilerDBConnection.pcc@%d: Data selected from Oracle was shortened	ORACLE error - error selecting from the ACS control plan compiled list.	Refer to ORACLE/application expert first (Check the following). 1) Verify that ORACLE is running through checking the status of the listener(lsnrctl) and restart ORACLE only if neccessary. 2) Check the environment variables and/or configuration files: ORACLE_SID(environment), tnsnames.ora(configuration file), listener.ora(configuration file). Verify that the username and password for the current machine is correct. 3) Observe startup output for errors. Finally contact support.	ACS
110008	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR getCallPlanDataNode=%d acsCompilerDBConnection.pcc@%d: Data selected from Oracle was shortened	ORACLE error - error selecting from the ACS control plan compiled list.	Refer to ORACLE/application expert first (Check the following). 1) Verify that ORACLE is running through checking the status of the listener(lsnrctl) and restart ORACLE only if neccessary. 2) Check the environment variables and/or configuration files: ORACLE_SID(environment), tnsnames.ora(configuration file), listener.ora(configuration file). Verify that the username and password for the current machine is correct. 3) Observe startup output for errors. Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110009	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR getCallPlanStructureNode=%d acsCompilerDBConnection.pcc@%d: Data selected from Oracle was shortened	ORACLE error - error selecting from the ACS control plan compiled list.	Refer to ORACLE/application expert first (Check the following). 1) Verify that ORACLE is running through checking the status of the listener(lsnrctl) and restart ORACLE only if neccessary. 2) Check the environment variables and/or configuration files: ORACLE_SID(environment), tnsnames.ora(configuration file), listener.ora(configuration file). Verify that the username and password for the current machine is correct. 3) Observe startup output for errors. Finally contact support.	ACS
110010	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR getCompiledCallPlanData=%d acsCompilerDBConnection.pcc@%d: Data selected from Oracle was shortened	ORACLE error - error selecting from the ACS control plan compiled list.	Refer to ORACLE/application expert first (Check the following). 1) Verify that ORACLE is running through checking the status of the listener(lsnrctl) and restart ORACLE only if neccessary. 2) Check the environment variables and/or configuration files: ORACLE_SID(environment), tnsnames.ora(configuration file), listener.ora(configuration file). Verify that the username and password for the current machine is correct. 3) Observe startup output for errors. Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110011	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR getFNDataDef=%d acsCompilerDBConnection.pcc@%d: Data selected from Oracle was shortened	ORACLE error - error selecting from the ACS control plan compiled list.	Refer to ORACLE/application expert first (Check the following). 1) Verify that ORACLE is running through checking the status of the listener(lsnrctl) and restart ORACLE only if neccessary. 2) Check the environment variables and/or configuration files: ORACLE_SID(environment), tnsnames.ora(configuration file), listener.ora(configuration file). Verify that the username and password for the current machine is correct. 3) Observe startup output for errors. Finally contact support.	ACS
110012	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR getFNMapping=%d acsCompilerDBConnection.pcc@%d: Data selected from Oracle was shortened	ORACLE error - error selecting from the ACS control plan compiled list.	Refer to ORACLE/application expert first (Check the following). 1) Verify that ORACLE is running through checking the status of the listener(lsnrctl) and restart ORACLE only if neccessary. 2) Check the environment variables and/or configuration files: ORACLE_SID(environment), tnsnames.ora(configuration file), listener.ora(configuration file). Verify that the username and password for the current machine is correct. 3) Observe startup output for errors. Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110013	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR getFNStructDef=%d acsCompilerDBConnection.pcc@%d: Data selected from Oracle was shortened	ORACLE error - error selecting from the ACS control plan compiled list.	Refer to ORACLE/application expert first (Check the following). 1) Verify that ORACLE is running through checking the status of the listener(lsnrctl) and restart ORACLE only if neccessary. 2) Check the environment variables and/or configuration files: ORACLE_SID(environment), tnsnames.ora(configuration file), listener.ora(configuration file). Verify that the username and password for the current machine is correct. 3) Observe startup output for errors. Finally contact support.	ACS
110014	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR getHoliday=%d acsCompilerDBConnection.pcc@%d: Data selected from Oracle was shortened	ORACLE error - error selecting from the ACS control plan compiled list.	Refer to ORACLE/application expert first (Check the following). 1) Verify that ORACLE is running through checking the status of the listener(lsnrctl) and restart ORACLE only if neccessary. 2) Check the environment variables and/or configuration files: ORACLE_SID(environment), tnsnames.ora(configuration file), listener.ora(configuration file). Verify that the username and password for the current machine is correct. 3) Observe startup output for errors. Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110015	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR getRegion=%d acsCompilerDBConnection.pcc@%d: Data selected from Oracle was shortened	ORACLE error - error selecting from the ACS control plan compiled list.	Refer to ORACLE/application expert first (Check the following). 1) Verify that ORACLE is running through checking the status of the listener(lsnrctl) and restart ORACLE only if neccessary. 2) Check the environment variables and/or configuration files: ORACLE_SID(environment), tnsnames.ora(configuration file), listener.ora(configuration file). Verify that the username and password for the current machine is correct. 3) Observe startup output for errors. Finally contact support.	ACS
110016	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR maskSignals=%d acsCompilerDaemon.cc@%d: Unable to mask Signals	ORACLE error - error selecting from the ACS control plan compiled list.	Refer to ORACLE/application expert first (Check the following). 1) Verify that ORACLE is running through checking the status of the listener(lsnrctl) and restart ORACLE only if neccessary. 2) Check the environment variables and/or configuration files: ORACLE_SID(environment), tnsnames.ora(configuration file), listener.ora(configuration file). Verify that the username and password for the current machine is correct. 3) Observe startup output for errors. Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110017	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR maskSignals=%d cmnSignals.c@%d:%z	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110018	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR unmaskSignals=%d acsCompilerDaemon.cc@%d: Unable to unmask Signals	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110019	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR unmaskSignals=%d cmnSignals.c@%d:%z	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110020	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR updateCompiledCallPlanStructure=%d acsCompilerDBConnection.pcc@%d: Compiled Structure too large, Max 65536 bytes	ORACLE error - error deleting from the ACS control plan compiled list.	Refer to ORACLE/application expert first (Check the following). 1) Verify that ORACLE is running through checking the status of the listener(lsnrctl) and restart ORACLE only if neccessary. 2) Check the environment variables and/or configuration files: ORACLE_SID(environment), tnsnames.ora(configuration file), listener.ora(configuration file). Verify that the username and password for the current machine is correct. 3) Observe startup output for errors. Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110021	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR updateUsage=%d acsCompilerDBConnection.pcc@%d:% z	ORACLE error - error selecting from the ACS control plan compiled list.	Refer to ORACLE/application expert first (Check the following). 1) Verify that ORACLE is running through checking the status of the listener(lsnrctl) and restart ORACLE only if neccessary. 2) Check the environment variables and/or configuration files: ORACLE_SID(environment), tnsnames.ora(configuration file), listener.ora(configuration file). Verify that the username and password for the current machine is correct. 3) Observe startup output for errors. Finally contact support.	ACS
110022	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR: ACS Plugin %s %d returned FALSE from sharedLibraryInit	acsCompilerDaemon shared library is missing/corrupt.	Assuming basic UNIX skills (Check the following). 1) Check validity and permissions of the acsStatsMaster shared library in /IN/service_packages/ACS/lib. 2) Verify the entry exists for this shared library in the ACS.conf file found in /IN/service_packages/ACS/etc.	ACS
110023	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR: Cannot catch SIGABRT	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110024	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR: Cannot catch SIGHUP	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110025	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR: Cannot catch SIGINT	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110026	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR: Cannot catch SIGTERM	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110027	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR: Compiler error number %d missing]!	Failed to compile this control plan.	Attempt to resave and recompile this control plan. Finally contact support.	ACS
110028	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR: Compiler error number %d not defined!	Failed to compile this control plan - unknown error number.	Attempt to resave and recompile this control plan. Finally contact support.	ACS
110029	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR: Could not find symbol sharedLibraryInit in ACS PluginZZZ	acsCompilerDaemon shared library is missing/corrupt.	Assuming basic UNIX skills (Check the following). 1)Check validity and permissions of the acsStatsMaster shared library in /IN/service_packages/ACS/lib. 2) Verify the entry exists for this shared library in the ACS.conf file found in /IN/service_packages/ACS/etc.	ACS
110030	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR: Could not load ACS PluginZZZ	acsCompilerDaemon shared library is missing/corrupt.	Assuming basic UNIX skills (Check the following). 1)Check validity and permissions of the acsStatsMaster shared library in /IN/service_packages/ACS/lib. 2) Verify the entry exists for this shared library in the ACS.conf file found in /IN/service_packages/ACS/etc.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110031	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR: Error deleting from ACS_COMPILE_LIST	ORACLE error - error deleting from the ACS control plan compiled list.	Refer to ORACLE/application expert first (Check the following). 1) Verify that ORACLE is running through checking the status of the listener(lsnrctl) and restart ORACLE only if neccessary. 2) Check the environment variables and/or configuration files: ORACLE_SID(environment), tnsnames.ora(configuration file), listener.ora(configuration file). Verify that the username and password for the current machine is correct. 3) Observe startup output for errors. Finally contact support.	ACS
110032	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR: Error selecting from compileListCursor (ACS_COMPILE_LIST)	ORACLE error - error selecting from the ACS control plan compiled list.	Refer to ORACLE/application expert first (Check the following). 1) Verify that ORACLE is running through checking the status of the listener(lsnrctl) and restart ORACLE only if neccessary. 2) Check the environment variables and/or configuration files: ORACLE_SID(environment), tnsnames.ora(configuration file), listener.ora(configuration file). Verify that the username and password for the current machine is correct. 3) Observe startup output for errors. Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110033	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR: Failed to connect to oracle as user %s %d (password hidden)	Cannot connect to ORACLE.	Refer to ORACLE/application expert first (Check the following). 1) Verify that ORACLE is running through checking the status of the listener(lsnrctl) and restart ORACLE only if neccessary. 2) Check the environment variables and/or configuration files: ORACLE_SID(environment), tnsnames.ora(configuration file), listener.ora(configuration file). Verify that the username and password for the current machine is correct. 3) Observe startup output for errors. Finally contact support.	ACS
110034	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) CRITICAL: Aiee! cmnPluginReleaseHandle received NULL handle!	Internal software error.	Contact support. No further information can be obtained.	ACS
110035	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) CRITICAL: cmnPlugin: error loading library %s %d:%z	acsCompilerDaemon shared library is missing/corrupt.	Assuming basic UNIX skills (Check the following). 1) Check validity and permissions of the acsStatsLocalSLEE shared library in /IN/service_packages/MOB_PP/lib	ACS
110036	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR: cmnDate::getLocalDate:%z	Internal software error.	No resolution. If problem persists then contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110037	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR: cmnProfileFindIndex: Profile corrupt (data pos misaligned)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110038	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR: cmnProfileFindIndex: Profile corrupt (length < 0)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110039	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR: cmnProfileFindIndex: Profile corrupt (offset + length > profileLength)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110040	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR: cmnProfileFindIndex: Profile corrupt (offset < 0)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110041	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR: cmnProfileFindIndex: Profile corrupt (offset > profileLength)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110042	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR: cmnProfileFindIndex: Profile corrupt (TOC end > profileLength)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110043	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR: cmnProfileFindTag: Profile corrupt (data pos misaligned)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110044	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR: cmnProfileFindTag: Profile corrupt (length < 0)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110045	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR: cmnProfileFindTag: Profile corrupt (offset + length > profileLength)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110046	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR: cmnProfileFindTag: Profile corrupt (offset < 0)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110047	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR: cmnProfileFindTag: Profile corrupt (offset > profileLength)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110048	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR: Remove tag: Corrupted, tag field data passes end of profile	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110049	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR: Remove tag: Corrupted, tag length begins before profile	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110050	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR: Remove tag: Corrupted, tag length field passes end of profile	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110051	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR: Update block corrupt. Item offset is negative. Creating empty block.	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110052	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR: Update block has no tags but is wrong size. Creating empty profile.	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110053	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR: Update profile corrupt. Field goes past profile block len.	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110054	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR: Update profile corrupt. Length goes past profile block len.	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110055	NOTICE	acsCompilerDaemon: acsCompilerDaemon(%d) NOTICE: gethostbyname:%z	Communications over the socket appears to have problems.	Refer to UNIX/application/LAN expert first (Check the following). 1) TCP/IP connection integrity. 2) Type netstat -na (see man netstat for more information) to determine the status of the listening socket for this connection. (Should be a configuration parameter). Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110056	NOTICE	acsCompilerDaemon: acsCompilerDaemon(%d) NOTICE: Select:%z	Communications over the socket appears to have problems.	Refer to UNIX/application/LAN expert first (Check the following). 1) TCP/IP connection integrity. 2) Type netstat -na (see man netstat for more information) to determine the status of the listening socket for this connection. (Should be a configuration parameter). Finally contact support.	ACS
110057	NOTICE	acsCompilerDaemon: acsCompilerDaemon(%d) NOTICE: socket:%z	Communications over the socket appears to have problems.	Refer to UNIX/application/LAN expert first (Check the following). 1) TCP/IP connection integrity. 2) Type netstat -na (see man netstat for more information) to determine the status of the listening socket for this connection. (Should be a configuration parameter). Finally contact support.	ACS
110058	WARNING	acsCompilerDaemon: acsCompilerDaemon(%d) WARNING: cmnPluginLookupFunction: could not find symbol %s %d::%s %d:%z	acsCompilerDaemon shared library is missing/corrupt.	Assuming basic UNIX skills (Check the following). 1) Check validity and permissions of the acsStatsMaster shared library in /IN/service_packages/ACS/lib. 2) Verify the entry exists for this shared library in the ACS.conf file found in /IN/service_packages/ACS/etc.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110059	WARNING	acsCompilerDaemon: acsCompilerDaemon(%d) WARNING: cmnPluginReleaseHandle: released already-released pluginZZZ	acsCompilerDaemon shared library is missing/corrupt.	Assuming basic UNIX skills (Check the following). 1) Check validity and permissions of the acsStatsMaster shared library in /IN/service_packages/ACS/lib. 2) Verify the entry exists for this shared library in the ACS.conf file found in /IN/service_packages/ACS/etc.	ACS
110060	WARNING	acsCompilerDaemon: acsCompilerDaemon(%d) WARNING: Macro %s %d not found.	This macro node has been encountered in a control plan but the implementation details for this macro node cannot be found.	Contact support. No further information can be obtained.	ACS
110061	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR: Could not stat() language index fileZZZ	Attempting to obtain the status of the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS
110062	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR: Could not load either the requested language file or Default.lang! Falling back to untranslated strings.	Attempting to open the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110063	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR: Could not read language index fileZZZ	Attempting to read the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS
110064	WARNING	acsCompilerDaemon: acsCompilerDaemon(%d) WARNING: cmnConfigGetStringVector: unable to openZZZ	Attempting to open the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS
110065	WARNING	acsCompilerDaemon: acsCompilerDaemon(%d) WARNING: Could not load language file %s %d! Falling back to Default.lang.	Attempting to read the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS
110066	WARNING	acsCompilerDaemon: acsCompilerDaemon(%d) WARNING: Could not reload language file %s %d! Staying with in-core copy.	Attempting to read the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110067	WARNING	acsCompilerDaemon: acsCompilerDaemon(%d) WARNING: getValue: unable to openZZZ	Attempting to read the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS
110068	WARNING	acsCompilerDaemon: acsCompilerDaemon(%d) WARNING: cmnConfigGetChar: %z	Attempting to read the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS
110069	WARNING	acsCompilerDaemon: acsCompilerDaemon(%d) WARNING: cmnConfigGetFlag: %z	Attempting to read the acsCompilerDaemon configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110070	WARNING	acsCompilerDaemon: acsCompilerDaemon(%d) WARNING: cmnConfigGetInteger: %z	Attempting to read the acsCompilerDaemon configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS
110071	WARNING	acsCompilerDaemon: acsCompilerDaemon(%d) WARNING: cmnConfigGetString: %z	Attempting to read the acsCompilerDaemon configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110072	WARNING	acsCompilerDaemon: acsCompilerDaemon(%d) WARNING: getConfig: No trailing : on sectionZZZ	Attempting to read the acsCompilerDaemon configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS
110073	WARNING	acsCompilerDaemon: acsCompilerDaemon(%d) WARNING: Language translation dictionary in %s %d contained an invalid mapping line (no unescaped = sign) on or about line %d	Invalid line found in the currently selected language translation file.	Modify this line in the currently selected language translation file found in /IN/html/SMS/language.	ACS
110074	WARNING	acsCompilerDaemon: acsCompilerDaemon(%d) WARNING: Language string not found in currently selected language database: %s %d	Invalid line found in the currently selected language translation file.	Modify this line in the currently selected language translation file found in /IN/html/SMS/language.	ACS
110075	CRITICAL	acsCompilerDaemon: acsCompilerDaemon(%d) CRITICAL: malloc() returned NULL in build_filename (cmnLang.cc)! Out of memory!	Insufficient memory to perform desired action due to internal software error.	Refer to UNIX/application expert first (Check the following). 1) Rogue processes consuming memory 2) Unusually large memory consumption for an individual binary. Finally contact support.	ACS
110076	CRITICAL	acsCompilerDaemon: acsCompilerDaemon(%d) CRITICAL: Out of memory in cmnLang.cc:processLine!	Insufficient memory to perform desired action due to internal software error.	Refer to UNIX/application expert first (Check the following). 1) Rogue processes consuming memory 2) Unusually large memory consumption for an individual binary. Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110077	CRITICAL	acsCompilerDaemon: acsCompilerDaemon(%d) NOTICE allocate=%d cmnRangeOciFetch.c@%d: out of memory	Insufficient memory to perform desired action due to internal software error.	Refer to UNIX/application expert first (Check the following). 1) Rogue processes consuming memory 2) Unusually large memory consumption for an individual binary. Finally contact support.	ACS
110078	CRITICAL	acsCompilerDaemon: acsCompilerDaemon(%d) WARNING strdup=%d loggedError.c@%d: out of memory	Insufficient memory to perform desired action due to internal software error.	Refer to UNIX/application expert first (Check the following). 1) Rogue processes consuming memory 2) Unusually large memory consumption for an individual binary. Finally contact support.	ACS
110079	NOTICE	acsCompilerDaemon: acsCompilerDaemon(%d) NOTICE oparse=%d cmnRangeOciFetch.c@%d:%z	Cannot connect to ORACLE.	Refer to ORACLE/application expert first (Check the following). 1) Verify that ORACLE is running through checking the status of the listener(lsnrctl) and restart ORACLE only if neccessary. 2) Check the environment variables and/or configuration files: ORACLE_SID(environment), tnsnames.ora(configuration file), listener.ora(configuration file). Verify that the username and password for the current machine is correct. 3) Observe startup output for errors. Finally contact support.	ACS
110080	NOTICE	acsCompilerDaemon: acsCompilerDaemon(%d) NOTICE: Startup Successful	Informational alarm - acsCompilerDaemon successfully started.	No resolution.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110081	NOTICE	acsCompilerDaemon: acsCompilerDaemon(%d) NOTICE getCompiledCallPlanStructure=%d acsCompilerDBConnection.pcc@%d: Data selected from Oracle was shortened	ORACLE error - error selecting from the ACS control plan compiled list.	Refer to ORACLE/application expert first (Check the following). 1) Verify that ORACLE is running through checking the status of the listener(lsnrctl) and restart ORACLE only if neccessary. 2) Check the environment variables and/or configuration files: ORACLE_SID(environment), tnsnames.ora(configuration file), listener.ora(configuration file). Verify that the username and password for the current machine is correct. 3) Observe startup output for errors. Finally contact support.	ACS
110082	NOTICE	acsCompilerDaemon: acsCompilerDaemon(%d) NOTICE: cmnConfigGetChar: %z	Attempting to read the acsLogEventDaemon configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110083	NOTICE	acsCompilerDaemon: acsCompilerDaemon(%d) NOTICE: cmnConfigGetFlag: %z	Attempting to read the acsLogEventDaemon configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS
110084	NOTICE	acsCompilerDaemon: acsCompilerDaemon(%d) NOTICE: cmnConfigGetInteger: %z	Attempting to read the acsLogEventDaemon configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110085	NOTICE	acsCompilerDaemon: acsCompilerDaemon(%d) NOTICE: cmnConfigGetString: %z	Attempting to read the acsLogEventDaemon configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS
110086	ERROR	acsLogEventDaemon: acsLogEventDaemon(%d) ERROR maskSignals=%d cmnSignals.c@%d:%z	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110087	ERROR	acsLogEventDaemon: acsLogEventDaemon(%d) ERROR unmaskSignals=%d cmnSignals.c@%d:%z	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110088	ERROR	acsLogEventDaemon: acsLogEventDaemon(%d) ERROR: ACS event log daemon cant close log file.)	Attempting to close the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS
110089	ERROR	acsLogEventDaemon: acsLogEventDaemon(%d) ERROR: ACS event log daemon failed to initialise (error retrieving log file name)	acsLogEventDaemon failed to start cannot retrieve logfile name.	No resolution.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110090	ERROR	acsLogEventDaemon: acsLogEventDaemon(%d) ERROR: ACS event log daemon failed to initialise Error opening log file: %s 112 Reason:%z	acsLogEventDaemon failed to start cannot open logfile.	No resolution.	ACS
110091	ERROR	acsLogEventDaemon: acsLogEventDaemon(%d) ERROR: ACS Plugin %s %d returned FALSE from sharedLibraryInit	acsCompilerDaemon shared library is missing/corrupt.	Assuming basic UNIX skills (Check the following). 1)Check validity and permissions of the acsStatsMaster shared library in /IN/service_packages/ACS/lib. 2) Verify the entry exists for this shared library in the ACS.conf file found in /IN/service_packages/ACS/etc.	ACS
110092	ERROR	acsLogEventDaemon: acsLogEventDaemon(%d) ERROR: Could not find symbol sharedLibraryInit in ACS PluginZZZ	acsCompilerDaemon shared library is missing/corrupt.	Assuming basic UNIX skills (Check the following). 1)Check validity and permissions of the acsStatsMaster shared library in /IN/service_packages/ACS/lib. 2) Verify the entry exists for this shared library in the ACS.conf file found in /IN/service_packages/ACS/etc.	ACS
110093	ERROR	acsLogEventDaemon: acsLogEventDaemon(%d) ERROR: Could not load ACS PluginZZZ	acsCompilerDaemon shared library is missing/corrupt.	Assuming basic UNIX skills (Check the following). 1)Check validity and permissions of the acsStatsMaster shared library in /IN/service_packages/ACS/lib. 2) Verify the entry exists for this shared library in the ACS.conf file found in /IN/service_packages/ACS/etc.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110094	ERROR	acsLogEventDaemon: acsLogEventDaemon(%d) ERROR: Failed to connect to oracle as user %s %d (password hidden)	Cannot connect to ORACLE.	Refer to ORACLE/application expert first (Check the following). 1) Verify that ORACLE is running through checking the status of the listener(lsnrctl) and restart ORACLE only if neccessary. 2) Check the environment variables and/or configuration files: ORACLE_SID(environment), tnsnames.ora(configuration file), listener.ora(configuration file). Verify that the username and password for the current machine is correct. 3) Observe startup output for errors. Finally contact support.	ACS
110095	ERROR	acsLogEventDaemon: acsLogEventDaemon(%d) ERROR: failed to initialise (cant set handler for SIGARLM)	acsLogEventDaemon failed to start.	No resolution.	ACS
110096	ERROR	acsLogEventDaemon: acsLogEventDaemon(%d) ERROR: failed to initialise (cant set handler for SIGINT)	acsLogEventDaemon failed to start.	No resolution.	ACS
110097	ERROR	acsLogEventDaemon: acsLogEventDaemon(%d) ERROR: failed to initialise (cant set handler for SIGQUIT)	acsLogEventDaemon failed to start.	No resolution.	ACS
110098	ERROR	acsLogEventDaemon: acsLogEventDaemon(%d) ERROR: failed to initialise (cant set handler for SIGTERM)	acsLogEventDaemon failed to start.	No resolution.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110099	ERROR	acsLogEventDaemon: acsLogEventDaemon(%d) ERROR: failed to initialise (cant set handler for SIGUSR1)	acsLogEventDaemon failed to start.	No resolution.	ACS
110100	ERROR	acsLogEventDaemon: acsLogEventDaemon(%d) ERROR: failed to initialise (cant write ipc log file %z)	acsLogEventDaemon failed to start.	No resolution.	ACS
110101	ERROR	acsLogEventDaemon: acsLogEventDaemon(%d) ERROR: File write error while writing to logfile -%z	Attempting to write to the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS
110102	ERROR	acsLogEventDaemon: acsLogEventDaemon(%d) ERROR: IPC resources lost (semaphore) - quitting	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110103	ERROR	acsLogEventDaemon: acsLogEventDaemon(%d) ERROR: IPC resources lost (shared mem) - quitting	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110104	ERROR	acsLogEventDaemon: acsLogEventDaemon(%d) CRITICAL: Aiee! cmnPluginReleaseHandle received NULL handle!	Internal software error.	Contact support. No further information can be obtained.	ACS
110105	ERROR	acsLogEventDaemon: acsLogEventDaemon(%d) CRITICAL: cmnPlugin: error loading library %s %d:%z	acsLogEventDaemon shared library is missing/corrupt.	Assuming basic UNIX skills (Check the following). 1) Check validity and permissions of the acsStatsLocalSLEE shared library in /IN/service_packages/MOB_PP/lib	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110106	ERROR	acsLogEventDaemon: acsLogEventDaemon(%d) ERROR: cmnDate::getLocalDate:%z	Internal software error.	No resolution. If problem persists then contact support.	ACS
110107	ERROR	acsLogEventDaemon: acsLogEventDaemon(%d) ERROR: cmnProfileFindIndex: Profile corrupt (data pos misaligned)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110108	ERROR	acsLogEventDaemon: acsLogEventDaemon(%d) ERROR: cmnProfileFindIndex: Profile corrupt (length < 0)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110109	ERROR	acsLogEventDaemon: acsLogEventDaemon(%d) ERROR: cmnProfileFindIndex: Profile corrupt (offset + length > profileLength)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110110	ERROR	acsLogEventDaemon: acsLogEventDaemon(%d) ERROR: cmnProfileFindIndex: Profile corrupt (offset < 0)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110111	ERROR	acsLogEventDaemon: acsLogEventDaemon(%d) ERROR: cmnProfileFindIndex: Profile corrupt (offset > profileLength)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110112	ERROR	acsLogEventDaemon: acsLogEventDaemon(%d) ERROR: cmnProfileFindIndex: Profile corrupt (TOC end > profileLength)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110113	ERROR	acsLogEventDaemon: acsLogEventDaemon(%d) ERROR: cmnProfileFindTag: Profile corrupt (data pos misaligned)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110114	ERROR	acsLogEventDaemon: acsLogEventDaemon(%d) ERROR: cmnProfileFindTag: Profile corrupt (length < 0)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110115	ERROR	acsLogEventDaemon: acsLogEventDaemon(%d) ERROR: cmnProfileFindTag: Profile corrupt (offset + length > profileLength)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110116	ERROR	acsLogEventDaemon: acsLogEventDaemon(%d) ERROR: cmnProfileFindTag: Profile corrupt (offset < 0)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110117	ERROR	acsLogEventDaemon: acsLogEventDaemon(%d) ERROR: cmnProfileFindTag: Profile corrupt (offset > profileLength)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110118	ERROR	acsLogEventDaemon: acsLogEventDaemon(%d) ERROR: Remove tag: Corrupted, tag field data passes end of profile	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110119	ERROR	acsLogEventDaemon: acsLogEventDaemon(%d) ERROR: Remove tag: Corrupted, tag length begins before profile	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110120	ERROR	acsLogEventDaemon: acsLogEventDaemon(%d) ERROR: Remove tag: Corrupted, tag length field passes end of profile	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110121	ERROR	acsLogEventDaemon: acsLogEventDaemon(%d) ERROR: Update block corrupt. Item offset is negative. Creating empty block.	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110122	ERROR	acsLogEventDaemon: acsLogEventDaemon(%d) ERROR: Update block has no tags but is wrong size. Creating empty profile.	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110123	ERROR	acsLogEventDaemon: acsLogEventDaemon(%d) ERROR: Update profile corrupt. Field goes past profile block len.	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110124	ERROR	acsLogEventDaemon: acsLogEventDaemon(%d) ERROR: Update profile corrupt. Length goes past profile block len.	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110125	NOTICE	acsLogEventDaemon: acsLogEventDaemon(%d) NOTICE: gethostbyname:%z	Communications over the socket appears to have problems.	Refer to UNIX/application/LAN expert first (Check the following). 1) TCP/IP connection integrity. 2) Type netstat -na (see man netstat for more information) to determine the status of the listening socket for this connection. (Should be a configuration parameter). Finally contact support.	ACS
110126	NOTICE	acsLogEventDaemon: acsLogEventDaemon(%d) NOTICE: Select:%z	Communications over the socket appears to have problems.	Refer to UNIX/application/LAN expert first (Check the following). 1) TCP/IP connection integrity. 2) Type netstat -na (see man netstat for more information) to determine the status of the listening socket for this connection. (Should be a configuration parameter). Finally contact support.	ACS
110127	NOTICE	acsLogEventDaemon: acsLogEventDaemon(%d) NOTICE: socket:%z	Communications over the socket appears to have problems.	Refer to UNIX/application/LAN expert first (Check the following). 1) TCP/IP connection integrity. 2) Type netstat -na (see man netstat for more information) to determine the status of the listening socket for this connection. (Should be a configuration parameter). Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110128	WARNING	acsLogEventDaemon: acsLogEventDaemon(%d) WARNING: cmnPluginLookupFunction: could not find symbol %s %d::%s %d:%z	acsProfile shared library is missing/corrupt.	Assuming basic UNIX skills (Check the following). 1) Check validity and permissions of the acsStatsMaster shared library in /IN/service_packages/ACS/lib. 2) Verify the entry exists for this shared library in the ACS.conf file found in /IN/service_packages/ACS/etc.	ACS
110129	WARNING	acsLogEventDaemon: acsLogEventDaemon(%d) WARNING: cmnPluginReleaseHandle: released already-released pluginZZZ	acsProfile shared library is missing/corrupt.	Assuming basic UNIX skills (Check the following). 1) Check validity and permissions of the acsStatsMaster shared library in /IN/service_packages/ACS/lib. 2) Verify the entry exists for this shared library in the ACS.conf file found in /IN/service_packages/ACS/etc.	ACS
110130	WARNING	acsLogEventDaemon: acsLogEventDaemon(%d) WARNING: Macro %s %d not found.	This macro node has been encountered in a control plan but the implementation details for this macro node cannot be found.	Contact support. No further information can be obtained.	ACS
110131	ERROR	acsLogEventDaemon: acsLogEventDaemon(%d) ERROR: Could not read language index fileZZZ	Attempting to read the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110132	ERROR	acsLogEventDaemon: acsLogEventDaemon(%d) ERROR: Could not load either the requested language file or Default.lang! Falling back to untranslated strings.	Attempting to read the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS
110133	WARNING	acsLogEventDaemon: acsLogEventDaemon(%d) WARNING: cmnConfigGetStringVector: unable to openZZZ	Attempting to open the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS
110134	WARNING	acsLogEventDaemon: acsLogEventDaemon(%d) WARNING: Could not load language file %s %d! Falling back to Default.lang.	Attempting to read the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS
110135	WARNING	acsLogEventDaemon: acsLogEventDaemon(%d) WARNING: Could not reload language file %s %d! Staying with in-core copy.	Attempting to read the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110136	WARNING	acsLogEventDaemon: acsLogEventDaemon(%d) WARNING: getValue: unable to openZZZ	Attempting to read the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS
110137	WARNING	acsLogEventDaemon: acsLogEventDaemon(%d) WARNING: cmnConfigGetChar: %z	Attempting to read the acsProfile configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS
110138	WARNING	acsLogEventDaemon: acsLogEventDaemon(%d) WARNING: cmnConfigGetFlag: %z	Attempting to read the acsProfile configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110139	WARNING	acsLogEventDaemon: acsLogEventDaemon(%d) WARNING: cmnConfigGetInteger: %z	Attempting to read the acsProfile configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS
110140	WARNING	acsLogEventDaemon: acsLogEventDaemon(%d) WARNING: cmnConfigGetString: %z	Attempting to read the acsProfile configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110141	WARNING	acsLogEventDaemon: acsLogEventDaemon(%d) WARNING: getConfig: No trailing : on sectionZZZ	Attempting to read the acsProfile configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS
110142	WARNING	acsLogEventDaemon: acsLogEventDaemon(%d) WARNING: Language translation dictionary in %s %d contained an invalid mapping line (no unescaped = sign) on or about line %d	Invalid line found in the currently selected language translation file.	Modify this line in the currently selected language translation file found in /IN/html/SMS/language.	ACS
110143	WARNING	acsLogEventDaemon: acsLogEventDaemon(%d) WARNING: Language string not found in currently selected language database: %s %d	Invalid line found in the currently selected language translation file.	Modify this line in the currently selected language translation file found in /IN/html/SMS/language.	ACS
110144	CRITICAL	acsLogEventDaemon: acsLogEventDaemon(%d) CRITICAL: malloc() returned NULL in build_filename (cmnLang.cc)! Out of memory!	Insufficient memory to perform desired action due to internal software error.	Refer to UNIX/application expert first (Check the following). 1) Rogue processes consuming memory 2) Unusually large memory consumption for an individual binary. Finally contact support.	ACS
110145	CRITICAL	acsLogEventDaemon: acsLogEventDaemon(%d) CRITICAL: Out of memory in cmnLang.cc:processLine!	Insufficient memory to perform desired action due to internal software error.	Refer to UNIX/application expert first (Check the following). 1) Rogue processes consuming memory 2) Unusually large memory consumption for an individual binary. Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110146	CRITICAL	acsLogEventDaemon: acsLogEventDaemon(%d) NOTICE allocate=%d cmnRangeOciFetch.c@%d: out of memory	Insufficient memory to perform desired action due to internal software error.	Refer to UNIX/application expert first (Check the following). 1) Rogue processes consuming memory 2) Unusually large memory consumption for an individual binary. Finally contact support.	ACS
110147	CRITICAL	acsLogEventDaemon: acsLogEventDaemon(%d) WARNING strdup=%d loggedError.c@%d: out of memory	Insufficient memory to perform desired action due to internal software error.	Refer to UNIX/application expert first (Check the following). 1) Rogue processes consuming memory 2) Unusually large memory consumption for an individual binary. Finally contact support.	ACS
110148	NOTICE	acsLogEventDaemon: acsLogEventDaemon(%d) NOTICE oparse=%d cmnRangeOciFetch.c@%d:%z	Cannot connect to ORACLE.	Refer to ORACLE/application expert first (Check the following). 1) Verify that ORACLE is running through checking the status of the listener(lsnrctl) and restart ORACLE only if neccessary. 2) Check the environment variables and/or configuration files: ORACLE_SID(environment), tnsnames.ora(configuration file), listener.ora(configuration file). Verify that the username and password for the current machine is correct. 3) Observe startup output for errors. Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110149	NOTICE	acsLogEventDaemon: acsLogEventDaemon(%d) NOTICE: cmnConfigGetChar: %z	Attempting to read the acsLogEventDaemon configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS
110150	NOTICE	acsLogEventDaemon: acsLogEventDaemon(%d) NOTICE: cmnConfigGetFlag: %z	Attempting to read the acsLogEventDaemon configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110151	NOTICE	acsLogEventDaemon: acsLogEventDaemon(%d) NOTICE: cmnConfigGetInteger: %z	Attempting to read the acsLogEventDaemon configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS
110152	NOTICE	acsLogEventDaemon: acsLogEventDaemon(%d) NOTICE: cmnConfigGetString: %z	Attempting to read the acsLogEventDaemon configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS
110153	ERROR	acsProfile: acsProfile(%d) ERROR maskSignals=%d cmnSignals.c@%d:%z	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110154	ERROR	acsProfile: acsProfile(%d) ERROR unmaskSignals=%d cmnSignals.c@%d:%z	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110155	ERROR	acsProfile: acsProfile(%d) ERROR: ACS Plugin %s %d returned FALSE from sharedLibraryInit	Error when trying to register this control plans feature node.	Contact support. No further information can be obtained.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110156	ERROR	acsProfile: acsProfile(%d) ERROR: Could not find symbol sharedLibraryInit in ACS PluginZZZ	acsStatsLocalSLEE shared library is missing/corrupt.	Assuming basic UNIX skills (Check the following). 1)Check validity and permissions of the acsStatsLocalSLEE shared library in /IN/service_packages/ACS/lib. 2) Verify the entry exists for this shared library in the ACS.conf file found in /IN/service_packages/ACS/etc.	ACS
110157	ERROR	acsProfile: acsProfile(%d) ERROR: Could not load ACS PluginZZZ	ACS Plugin shared library is missing/corrupt.	Assuming basic UNIX skills (Check the following). 1)Check validity and permissions of the ACS Plugin shared library in /IN/service_packages/ACS/lib. 2) Verify the entry exists for this shared library in the ACS.conf file found in /IN/service_packages/ACS/etc.	ACS
110158	ERROR	acsProfile: acsProfile(%d) ERROR: Failed to connect to oracle as user %s %d (password hidden)	Cannot connect to ORACLE.	Refer to ORACLE/application expert first (Check the following). 1)Verify that ORACLE is running through checking the status of the listener(lsnrctl) and restart ORACLE only if neccessary. 2) Check the environment variables and/or configuration files: ORACLE_SID(environment), tnsnames.ora(configuration file), listener.ora(configuration file). Verify that the username and password for the current machine is correct. 3) Observe startup output for errors. Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110159	ERROR	acsProfile: acsProfile(%d) CRITICAL: Aiee! cmnPluginReleaseHandle received NULL handle!	Internal software error.	Contact support. No further information can be obtained.	ACS
110160	ERROR	acsProfile: acsProfile(%d) CRITICAL: cmnPlugin: error loading library %s %d:%z	acsProfile shared library is missing/corrupt.	Assuming basic UNIX skills (Check the following). 1)Check validity and permissions of the acsStatsLocalSLEE shared library in /IN/service_packages/MOB_PP/lib	ACS
110161	ERROR	acsProfile: acsProfile(%d) ERROR: cmnDate::getLocalDate:%z	Internal software error.	No resolution. If problem persists then contact support.	ACS
110162	ERROR	acsProfile: acsProfile(%d) ERROR: cmnProfileFindIndex: Profile corrupt (data pos misaligned)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110163	ERROR	acsProfile: acsProfile(%d) ERROR: cmnProfileFindIndex: Profile corrupt (length < 0)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110164	ERROR	acsProfile: acsProfile(%d) ERROR: cmnProfileFindIndex: Profile corrupt (offset + length > profileLength)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110165	ERROR	acsProfile: acsProfile(%d) ERROR: cmnProfileFindIndex: Profile corrupt (offset < 0)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110166	ERROR	acsProfile: acsProfile(%d) ERROR: cmnProfileFindIndex: Profile corrupt (offset > profileLength)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110167	ERROR	acsProfile: acsProfile(%d) ERROR: cmnProfileFindIndex: Profile corrupt (TOC end > profileLength)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110168	ERROR	acsProfile: acsProfile(%d) ERROR: cmnProfileFindTag: Profile corrupt (data pos misaligned)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110169	ERROR	acsProfile: acsProfile(%d) ERROR: cmnProfileFindTag: Profile corrupt (length < 0)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110170	ERROR	acsProfile: acsProfile(%d) ERROR: cmnProfileFindTag: Profile corrupt (offset + length > profileLength)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110171	ERROR	acsProfile: acsProfile(%d) ERROR: cmnProfileFindTag: Profile corrupt (offset < 0)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110172	ERROR	acsProfile: acsProfile(%d) ERROR: cmnProfileFindTag: Profile corrupt (offset > profileLength)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110173	ERROR	acsProfile: acsProfile(%d) ERROR: Remove tag: Corrupted, tag field data passes end of profile	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110174	ERROR	acsProfile: acsProfile(%d) ERROR: Remove tag: Corrupted, tag length begins before profile	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110175	ERROR	acsProfile: acsProfile(%d) ERROR: Remove tag: Corrupted, tag length field passes end of profile	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110176	ERROR	acsProfile: acsProfile(%d) ERROR: Update block corrupt. Item offset is negative. Creating empty block.	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110177	ERROR	acsProfile: acsProfile(%d) ERROR: Update block has no tags but is wrong size. Creating empty profile.	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110178	ERROR	acsProfile: acsProfile(%d) ERROR: Update profile corrupt. Field goes past profile block len.	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110179	ERROR	acsProfile: acsProfile(%d) ERROR: Update profile corrupt. Length goes past profile block len.	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110180	NOTICE	acsProfile: acsProfile(%d) NOTICE: gethostbyname:%z	Communications over the socket appears to have problems.	Refer to UNIX/application/LAN expert first (Check the following). 1) TCP/IP connection integrity. 2) Type netstat -na (see man netstat for more information) to determine the status of the listening socket for this connection. (Should be a configuration parameter). Finally contact support.	ACS
110181	NOTICE	acsProfile: acsProfile(%d) NOTICE: Select:%z	Communications over the socket appears to have problems.	Refer to UNIX/application/LAN expert first (Check the following). 1) TCP/IP connection integrity. 2) Type netstat -na (see man netstat for more information) to determine the status of the listening socket for this connection. (Should be a configuration parameter). Finally contact support.	ACS
110182	NOTICE	acsProfile: acsProfile(%d) NOTICE: socket:%z	Communications over the socket appears to have problems.	Refer to UNIX/application/LAN expert first (Check the following). 1) TCP/IP connection integrity. 2) Type netstat -na (see man netstat for more information) to determine the status of the listening socket for this connection. (Should be a configuration parameter). Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110183	WARNING	acsProfile: acsProfile(%d) WARNING: cmnPluginLookupFunction: could not find symbol %s %d::%s %d:%z	acsProfile shared library is missing/corrupt.	Assuming basic UNIX skills (Check the following). 1) Check validity and permissions of the acsStatsMaster shared library in /IN/service_packages/ACS/lib. 2) Verify the entry exists for this shared library in the ACS.conf file found in /IN/service_packages/ACS/etc.	ACS
110184	WARNING	acsProfile: acsProfile(%d) WARNING: cmnPluginReleaseHandle: released already-released pluginZZZ	acsProfile shared library is missing/corrupt.	Assuming basic UNIX skills (Check the following). 1) Check validity and permissions of the acsStatsMaster shared library in /IN/service_packages/ACS/lib. 2) Verify the entry exists for this shared library in the ACS.conf file found in /IN/service_packages/ACS/etc.	ACS
110185	WARNING	acsProfile: acsProfile(%d) WARNING: Macro %s %d not found.	This macro node has been encountered in a control plan but the implementation details for this macro node cannot be found.	Contact support. No further information can be obtained.	ACS
110186	ERROR	acsProfile: acsProfile(%d) ERROR: Could not stat() language index fileZZZ	Attempting to obtain the status of the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110187	ERROR	acsProfile: acsProfile(%d) ERROR: Could not load either the requested language file or Default.lang! Falling back to untranslated strings.	Attempting to open the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS
110188	ERROR	acsProfile: acsProfile(%d) ERROR: Could not read language index fileZZZ	Attempting to read the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS
110189	WARNING	acsProfile: acsProfile(%d) WARNING: cmnConfigGetStringVector: unable to openZZZ	Attempting to open the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS
110190	WARNING	acsProfile: acsProfile(%d) WARNING: Could not load language file %s %d! Falling back to Default.lang.	Attempting to read the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110191	WARNING	acsProfile: acsProfile(%d) WARNING: Could not reload language file %s %d! Staying with in-core copy.	Attempting to read the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS
110192	WARNING	acsProfile: acsProfile(%d) WARNING: getValue: unable to openZZZ	Attempting to read the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS
110193	WARNING	acsProfile: acsProfile(%d) WARNING: cmnConfigGetChar: %z	Attempting to read the acsProfile configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110194	WARNING	acsProfile: acsProfile(%d) WARNING: cmnConfigGetFlag: %z	Attempting to read the acsProfile configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS
110195	WARNING	acsProfile: acsProfile(%d) WARNING: cmnConfigGetInteger: %z	Attempting to read the acsProfile configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110196	WARNING	acsProfile: acsProfile(%d) WARNING: cmnConfigGetString: %z	Attempting to read the acsProfile configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS
110197	WARNING	acsProfile: acsProfile(%d) WARNING: getConfig: No trailing : on sectionZZZ	Attempting to read the acsProfile configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS
110198	WARNING	acsProfile: acsProfile(%d) WARNING: Language translation dictionary in %s %d contained an invalid mapping line (no unescaped = sign) on or about line %d	Invalid line found in the currently selected language translation file.	Modify this line in the currently selected language translation file found in /IN/html/SMS/language.	ACS
110199	WARNING	acsProfile: acsProfile(%d) WARNING: Language string not found in currently selected language database: %s %d	Invalid line found in the currently selected language translation file.	Modify this line in the currently selected language translation file found in /IN/html/SMS/language.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110200	CRITICAL	acsProfile: acsProfile(%d) CRITICAL: malloc() returned NULL in build_filename (cmnLang.cc)! Out of memory!	Insufficient memory to perform desired action due to internal software error.	Refer to UNIX/application expert first (Check the following). 1) Rogue processes consuming memory 2) Unusually large memory consumption for an individual binary. Finally contact support.	ACS
110201	CRITICAL	acsProfile: acsProfile(%d) CRITICAL: Out of memory in cmnLang.cc:processLine!	Insufficient memory to perform desired action due to internal software error.	Refer to UNIX/application expert first (Check the following). 1) Rogue processes consuming memory 2) Unusually large memory consumption for an individual binary. Finally contact support.	ACS
110202	CRITICAL	acsProfile: acsProfile(%d) NOTICE allocate=%d cmnRangeOciFetch.c@%d: out of memory	Insufficient memory to perform desired action due to internal software error.	Refer to UNIX/application expert first (Check the following). 1) Rogue processes consuming memory 2) Unusually large memory consumption for an individual binary. Finally contact support.	ACS
110203	CRITICAL	acsProfile: acsProfile(%d) WARNING strdup=%d loggedError.c@%d: out of memory	Insufficient memory to perform desired action due to internal software error.	Refer to UNIX/application expert first (Check the following). 1) Rogue processes consuming memory 2) Unusually large memory consumption for an individual binary. Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110204	NOTICE	acsProfile: acsProfile(%d) NOTICE oparse=%d cmnRangeOciFetch.c@%d:%z	Cannot connect to ORACLE.	Refer to ORACLE/application expert first (Check the following). 1) Verify that ORACLE is running through checking the status of the listener(lsnrctl) and restart ORACLE only if neccessary. 2) Check the environment variables and/or configuration files: ORACLE_SID(environment), tnsnames.ora(configuration file), listener.ora(configuration file). Verify that the username and password for the current machine is correct. 3) Observe startup output for errors. Finally contact support.	ACS
110205	NOTICE	acsProfile: acsProfile(%d) NOTICE: cmnConfigGetChar: %z	Attempting to read the acsProfile configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110206	NOTICE	acsProfile: acsProfile(%d) NOTICE: cmnConfigGetFlag: %z	Attempting to read the acsProfileconfiguration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS
110207	NOTICE	acsProfile: acsProfile(%d) NOTICE: cmnConfigGetInteger: %z	Attempting to read the acsProfile configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110208	NOTICE	acsProfile: acsProfile(%d) NOTICE: cmnConfigGetString: %z	Attempting to read the acsProfile configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS
110209	ERROR	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) CRITICAL: acsStatisticsDBInserter: recv retrieved %d timesZZZ	Communications over the socket appears to have problems.	Refer to UNIX/application/LAN expert first (Check the following). 1) TCP/IP connection integrity. 2) Type netstat -na (see man netstat for more information) to determine the status of the listening socket for this connection. (Should be a configuration parameter). Finally contact support.	ACS
110210	ERROR	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) ERROR maskSignals=%d cmnSignals.c@%d:%z	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110211	ERROR	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) ERROR unmaskSignals=%d cmnSignals.c@%d:%z	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110212	ERROR	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) ERROR: ACS Plugin %s %d returned FALSE from sharedLibraryInit	Error when trying to register this control plans feature node.	Contact support. No further information can be obtained.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110213	ERROR	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) ERROR: Could not find symbol sharedLibraryInit in ACS PluginZZZ	acsStatsLocalSLEE shared library is missing/corrupt.	Assuming basic UNIX skills (Check the following). 1)Check validity and permissions of the acsStatsLocalSLEE shared library in /IN/service_packages/ACS/lib. 2) Verify the entry exists for this shared library in the ACS.conf file found in /IN/service_packages/ACS/etc.	ACS
110214	ERROR	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) ERROR: Could not load ACS PluginZZZ	ACS Plugin shared library is missing/corrupt.	Assuming basic UNIX skills (Check the following). 1)Check validity and permissions of the ACS Plugin shared library in /IN/service_packages/ACS/lib. 2) Verify the entry exists for this shared library in the ACS.conf file found in /IN/service_packages/ACS/etc.	ACS
110215	ERROR	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) ERROR: Failed to connect to oracle as user %s %d (password hidden)	Cannot connect to ORACLE.	Refer to ORACLE/application expert first (Check the following). 1)Verify that ORACLE is running through checking the status of the listener(lsnrctl) and restart ORACLE only if neccessary. 2) Check the environment variables and/or configuration files: ORACLE_SID(environment), tnsnames.ora(configuration file), listener.ora(configuration file). Verify that the username and password for the current machine is correct. 3) Observe startup output for errors. Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110216	ERROR	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) CRITICAL: Aiee! cmnPluginReleaseHandle received NULL handle!	Internal software error.	Contact support. No further information can be obtained.	ACS
110217	ERROR	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) CRITICAL: cmnPlugin: error loading library %s %d:%z	acsStatisticsDBInser ter shared library is missing/corrupt.	Assuming basic UNIX skills (Check the following). 1)Check validity and permissions of the acsStatsLocalSLEE shared library in /IN/service_packages/MOB_PP/lib	ACS
110218	ERROR	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) ERROR: cmnDate::getLocalDate:%z	Internal software error.	No resolution. If problem persists then contact support.	ACS
110219	ERROR	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) ERROR: cmnProfileFindIndex: Profile corrupt (data pos misaligned)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110220	ERROR	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) ERROR: cmnProfileFindIndex: Profile corrupt (length < 0)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110221	ERROR	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) ERROR: cmnProfileFindIndex: Profile corrupt (offset + length > profileLength)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110222	ERROR	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) ERROR: cmnProfileFindIndex: Profile corrupt (offset < 0)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110223	ERROR	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) ERROR: cmnProfileFindIndex: Profile corrupt (offset > profileLength)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110224	ERROR	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) ERROR: cmnProfileFindIndex: Profile corrupt (TOC end > profileLength)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110225	ERROR	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) ERROR: cmnProfileFindTag: Profile corrupt (data pos misaligned)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110226	ERROR	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) ERROR: cmnProfileFindTag: Profile corrupt (length < 0)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110227	ERROR	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) ERROR: cmnProfileFindTag: Profile corrupt (offset + length > profileLength)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110228	ERROR	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) ERROR: cmnProfileFindTag: Profile corrupt (offset < 0)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110229	ERROR	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) ERROR: cmnProfileFindTag: Profile corrupt (offset > profileLength)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110230	ERROR	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) ERROR: Remove tag: Corrupted, tag field data passes end of profile	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110231	ERROR	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) ERROR: Remove tag: Corrupted, tag length begins before profile	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110232	ERROR	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) ERROR: Remove tag: Corrupted, tag length field passes end of profile	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110233	ERROR	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) ERROR: Update block corrupt. Item offset is negative. Creating empty block.	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110234	ERROR	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) ERROR: Update block has no tags but is wrong size. Creating empty profile.	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110235	ERROR	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) ERROR: Update profile corrupt. Field goes past profile block len.	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110236	ERROR	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) ERROR: Update profile corrupt. Length goes past profile block len.	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110237	NOTICE	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) NOTICE: gethostbyname:%z	Communications over the socket appears to have problems.	Refer to UNIX/application/LAN expert first (Check the following). 1) TCP/IP connection integrity. 2) Type netstat -na (see man netstat for more information) to determine the status of the listening socket for this connection. (Should be a configuration parameter). Finally contact support.	ACS
110238	NOTICE	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) NOTICE: Select:%z	Communications over the socket appears to have problems.	Refer to UNIX/application/LAN expert first (Check the following). 1) TCP/IP connection integrity. 2) Type netstat -na (see man netstat for more information) to determine the status of the listening socket for this connection. (Should be a configuration parameter). Finally contact support.	ACS
110239	NOTICE	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) NOTICE: socket:%z	acsStatisticsDBInserter shared library is missing/corrupt.	Assuming basic UNIX skills (Check the following). 1) Check validity and permissions of the acsStatsMaster shared library in /IN/service_packages/ACS/lib. 2) Verify the entry exists for this shared library in the ACS.conf file found in /IN/service_packages/ACS/etc.	ACS
110240	WARNING	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) WARNING: cmnPluginLookupFunction: could not find symbol %s %d::%s %d:%z	This macro node has been encountered in a control plan but the implementation details for this macro node cannot be found.	Contact support. No further information can be obtained.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110241	WARNING	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) WARNING: cmnPluginReleaseHandle: released already-released pluginZZZ	Attempting to obtain the status of the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS
110242	WARNING	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) WARNING: Macro %s %d not found.	Attempting to open the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS
110243	ERROR	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) ERROR: Could not stat() language index fileZZZ	Attempting to read the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS
110244	ERROR	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) ERROR: Could not load either the requested language file or Default.lang! Falling back to untranslated strings.	Attempting to open the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110245	ERROR	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) ERROR: Could not read language index fileZZZ	Attempting to read the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS
110246	WARNING	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) WARNING: cmnConfigGetStringVector: unable to openZZZ	Attempting to read the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS
110247	WARNING	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) WARNING: Could not load language file %s %d! Falling back to Default.lang.	Attempting to read the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS
110248	WARNING	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) WARNING: Could not reload language file %s %d! Staying with in-core copy.	Attempting to read the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110249	WARNING	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) WARNING: getValue: unable to openZZZ	Attempting to read the acsStatisticsDBInser ter configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS
110250	WARNING	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) WARNING: cmnConfigGetChar: %z	Attempting to read the acsStatisticsDBInser ter configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110251	WARNING	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) WARNING: cmnConfigGetFlag: %z	Attempting to read the acsStatisticsDBInserter configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS
110252	WARNING	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) WARNING: cmnConfigGetInteger: %z	Attempting to read the acsStatisticsDBInserter configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS
110253	WARNING	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) WARNING: cmnConfigGetString: %z	Invalid line found in the currently selected language translation file.	Modify this line in the currently selected language translation file found in /IN/html/SMS/language.	ACS
110254	WARNING	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) WARNING: getConfig: No trailing : on sectionZZZ	Invalid line found in the currently selected language translation file.	Modify this line in the currently selected language translation file found in /IN/html/SMS/language.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110255	WARNING	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) WARNING: Language translation dictionary in %s %d contained an invalid mapping line (no unescaped = sign) on or about line %d	Insufficient memory to perform desired action due to internal software error.	Refer to UNIX/application expert first (Check the following). 1) Rogue processes consuming memory 2) Unusually large memory consumption for an individual binary. Finally contact support.	ACS
110256	WARNING	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) WARNING: Language string not found in currently selected language database: %s %d	Insufficient memory to perform desired action due to internal software error.	Refer to UNIX/application expert first (Check the following). 1) Rogue processes consuming memory 2) Unusually large memory consumption for an individual binary. Finally contact support.	ACS
110257	CRITICAL	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) CRITICAL: malloc() returned NULL in build_filename (cmnLang.cc)! Out of memory!	Insufficient memory to perform desired action due to internal software error.	Refer to UNIX/application expert first (Check the following). 1) Rogue processes consuming memory 2) Unusually large memory consumption for an individual binary. Finally contact support.	ACS
110258	CRITICAL	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) CRITICAL: Out of memory in cmnLang.cc:processLine!	Insufficient memory to perform desired action due to internal software error.	Refer to UNIX/application expert first (Check the following). 1) Rogue processes consuming memory 2) Unusually large memory consumption for an individual binary. Finally contact support.	ACS
110259	CRITICAL	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) NOTICE allocate=%d cmnRangeOciFetch.c@%d: out of memory	Insufficient memory to perform desired action due to internal software error.	Refer to UNIX/application expert first (Check the following). 1) Rogue processes consuming memory 2) Unusually large memory consumption for an individual binary. Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110260	CRITICAL	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) WARNING strdup=%d loggedError.c@%d: out of memory	Insufficient memory to perform desired action due to internal software error.	Refer to UNIX/application expert first (Check the following). 1) Rogue processes consuming memory 2) Unusually large memory consumption for an individual binary. Finally contact support.	ACS
110261	NOTICE	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) NOTICE oparse=%d cmnRangeOciFetch.c@%d:%z	Cannot connect to ORACLE.	Refer to ORACLE/application expert first (Check the following). 1) Verify that ORACLE is running through checking the status of the listener(lsnrctl) and restart ORACLE only if necessary. 2) Check the environment variables and/or configuration files: ORACLE_SID(environment), tnsnames.ora(configuration file), listener.ora(configuration file). Verify that the username and password for the current machine is correct. 3) Observe startup output for errors. Finally contact support.	ACS
110262	NOTICE	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) NOTICE: acsStatisticsDBInserter: restart failed	Informational alarm - acsStatisticsDBInserter restart failed.	No resolution.	ACS
110263	CRITICAL	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) NOTICE: malloc error	Insufficient memory to perform desired action due to internal software error.	Refer to UNIX/application expert first (Check the following). 1) Rogue processes consuming memory 2) Unusually large memory consumption for an individual binary. Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110264	NOTICE	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) NOTICE: restart: Unable to handle signal	Informational alarm - acsStatisticsDBInser ter restarting.	No resolution.	ACS
110265	NOTICE	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) NOTICE: acsStatisticsDBInserter: %s %d retried %d times	Informational alarm - acsStatisticsDBInser ter has restarted this many times.	No resolution.	ACS
110266	NOTICE	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) NOTICE: cant catch SIGABRT	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110267	NOTICE	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) NOTICE: cant catch SIGHUP	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110268	NOTICE	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) NOTICE: connect:%z	Communications over the socket appears to have problems.	Refer to UNIX/application/LAN expert first (Check the following). 1) TCP/IP connection integrity. 2) Type netstat -na (see man netstat for more information) to determine the status of the listening socket for this connection. (Should be a configuration parameter). Finally contact support.	ACS
110269	NOTICE	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) NOTICE: File can not be opened	Attempting to read the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110270	NOTICE	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) NOTICE: recv timed-out	Communications over the socket appears to have problems.	Refer to UNIX/application/LAN expert first (Check the following). 1) TCP/IP connection integrity. 2) Type netstat -na (see man netstat for more information) to determine the status of the listening socket for this connection. (Should be a configuration parameter). Finally contact support.	ACS
110271	NOTICE	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) NOTICE: Retry limit reached. ExitingZZZ	Informational alarm - acsStatisticsDBInserter restart limit reached.	No resolution.	ACS
110272	NOTICE	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) NOTICE: Startup SuccessfulZZZ	Informational alarm - acsStatisticsDBInserter successfully started.	No resolution.	ACS
110273	NOTICE	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) NOTICE: strdup error	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110274	NOTICE	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) NOTICE: cmnConfigGetChar: %z	Attempting to read the acsStatisticsDBInserter configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110275	NOTICE	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) NOTICE: cmnConfigGetFlag: %z	Attempting to read the acsStatisticsDBInserter configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS
110276	NOTICE	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) NOTICE: cmnConfigGetInteger: %z	Attempting to read the acsStatisticsDBInserter configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110277	NOTICE	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) NOTICE: cmnConfigGetString: %z	Attempting to read the acsStatisticsDBInserter configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS
110278	NOTICE	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) NOTICE: cant catch SIGTERM	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110279	NOTICE	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) NOTICE: Config file error	Attempting to read the acsStatisticsDBInserter configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS
110280	NOTICE	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) NOTICE: This signal should not be caught	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110281	ERROR	acsStatsLocal: acsStatsLocal(%d) CRITICAL: listen() error:%z	Communications over the socket appears to have problems.	Refer to UNIX/application/LAN expert first (Check the following). 1) TCP/IP connection integrity. 2) Type netstat -na (see man netstat for more information) to determine the status of the listening socket for this connection. (Should be a configuration parameter). Finally contact support.	ACS
110282	ERROR	acsStatsLocal: acsStatsLocal(%d) CRITICAL: signal(), error = SIGERR	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110283	ERROR	acsStatsLocal: acsStatsLocal(%d) CRITICAL: socket() error:%z	Communications over the socket appears to have problems.	Refer to UNIX/application/LAN expert first (Check the following). 1) TCP/IP connection integrity. 2) Type netstat -na (see man netstat for more information) to determine the status of the listening socket for this connection. (Should be a configuration parameter). Finally contact support.	ACS
110284	ERROR	acsStatsLocal: acsStatsLocal(%d) ERROR maskSignals=%d cmnSignals.c@%d:%z	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110285	ERROR	acsStatsLocal: acsStatsLocal(%d) ERROR unmaskSignals=%d cmnSignals.c@%d:%z	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110286	ERROR	acsStatsLocal: acsStatsLocal(%d) ERROR: ACS Plugin %s %d returned FALSE from sharedLibraryInit	Error when trying to register this control plans feature node.	Contact support. No further information can be obtained.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110287	ERROR	acsStatsLocal: acsStatsLocal(%d) ERROR: close() error:%z	acsStatsLocal shared library is missing/corrupt.	Assuming basic UNIX skills (Check the following). 1)Check validity and permissions of the acsStatsLocalSLEE shared library in /IN/service_packages/ACS/lib. 2) Verify the entry exists for this shared library in the ACS.conf file found in /IN/service_packages/ACS/etc.	ACS
110288	ERROR	acsStatsLocal: acsStatsLocal(%d) ERROR: Could not find symbol sharedLibraryInit in ACS PluginZZZ	acsStatsLocal shared library is missing/corrupt.	Assuming basic UNIX skills (Check the following). 1)Check validity and permissions of the acsStatsLocalSLEE shared library in /IN/service_packages/ACS/lib. 2) Verify the entry exists for this shared library in the ACS.conf file found in /IN/service_packages/ACS/etc.	ACS
110289	ERROR	acsStatsLocal: acsStatsLocal(%d) ERROR: Could not load ACS PluginZZZ	ACS Plugin shared library is missing/corrupt.	Assuming basic UNIX skills (Check the following). 1)Check validity and permissions of the ACS Plugin shared library in /IN/service_packages/ACS/lib. 2) Verify the entry exists for this shared library in the ACS.conf file found in /IN/service_packages/ACS/etc.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110290	ERROR	acsStatsLocal: acsStatsLocal(%d) ERROR: Failed to connect to oracle as user %s %d (password hidden)	Cannot connect to ORACLE.	Refer to ORACLE/application expert first (Check the following). 1) Verify that ORACLE is running through checking the status of the listener(lsnrctl) and restart ORACLE only if neccessary. 2) Check the environment variables and/or configuration files: ORACLE_SID(environment), tnsnames.ora(configuration file), listener.ora(configuration file). Verify that the username and password for the current machine is correct. 3) Observe startup output for errors. Finally contact support.	ACS
110291	ERROR	acsStatsLocal: acsStatsLocal(%d) ERROR: FIFO or Socket has died, SIGPIPE received	Communications over the socket appears to have problems.	Refer to UNIX/application/LAN expert first (Check the following). 1) TCP/IP connection integrity. 2) Type netstat -na (see man netstat for more information) to determine the status of the listening socket for this connection. (Should be a configuration parameter). Finally contact support.	ACS
110292	ERROR	acsStatsLocal: acsStatsLocal(%d) ERROR: fork() error:%z	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110293	ERROR	acsStatsLocal: acsStatsLocal(%d) ERROR: recv() error:%z	Communications over the socket appears to have problems.	Refer to UNIX/application/LAN expert first (Check the following). 1) TCP/IP connection integrity. 2) Type netstat -na (see man netstat for more information) to determine the status of the listening socket for this connection. (Should be a configuration parameter). Finally contact support.	ACS
110294	ERROR	acsStatsLocal: acsStatsLocal(%d) ERROR: semctl() error:%z	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110295	ERROR	acsStatsLocal: acsStatsLocal(%d) ERROR: semget() error:%z	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110296	ERROR	acsStatsLocal: acsStatsLocal(%d) ERROR: semop() error:%z	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110297	ERROR	acsStatsLocal: acsStatsLocal(%d) ERROR: send() error:%z	Communications over the socket appears to have problems.	Refer to UNIX/application/LAN expert first (Check the following). 1) TCP/IP connection integrity. 2) Type netstat -na (see man netstat for more information) to determine the status of the listening socket for this connection. (Should be a configuration parameter). Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110298	ERROR	acsStatsLocal: acsStatsLocal(%d) ERROR: send() errno: %d	Communications over the socket appears to have problems.	Refer to UNIX/application/LAN expert first (Check the following). 1) TCP/IP connection integrity. 2) Type netstat -na (see man netstat for more information) to determine the status of the listening socket for this connection. (Should be a configuration parameter). Finally contact support.	ACS
110299	ERROR	acsStatsLocal: acsStatsLocal(%d) ERROR: shmat() error:%z	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110300	ERROR	acsStatsLocal: acsStatsLocal(%d) ERROR: shmctl() error:%z	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110301	ERROR	acsStatsLocal: acsStatsLocal(%d) ERROR: shmget() error:%z	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110302	WARNING	acsStatsLocal: acsStatsLocal(%d) WARNING: acsStatsLocal: Exit with status %d	acsStatsLocal exiting with this status.	No resolution.	ACS
110303	ERROR	acsStatsLocal: acsStatsLocal(%d) CRITICAL: Aiee! cmnPluginReleaseHandle received NULL handle!	Internal software error.	Contact support. No further information can be obtained.	ACS
110304	ERROR	acsStatsLocal: acsStatsLocal(%d) CRITICAL: cmnPlugin: error loading library %s %d:%z	acsStatsLocal shared library is missing/corrupt.	Assuming basic UNIX skills (Check the following). 1) Check validity and permissions of the acsStatsLocalSLEE shared library in /IN/service_packages/MOB_PP/lib	ACS
110305	ERROR	acsStatsLocal: acsStatsLocal(%d) ERROR: cmnDate::getLocalDate:%z	Internal software error.	No resolution. If problem persists then contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110306	ERROR	acsStatsLocal: acsStatsLocal(%d) ERROR: cmnProfileFindIndex: Profile corrupt (data pos misaligned)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110307	ERROR	acsStatsLocal: acsStatsLocal(%d) ERROR: cmnProfileFindIndex: Profile corrupt (length < 0)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110308	ERROR	acsStatsLocal: acsStatsLocal(%d) ERROR: cmnProfileFindIndex: Profile corrupt (offset + length > profileLength)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110309	ERROR	acsStatsLocal: acsStatsLocal(%d) ERROR: cmnProfileFindIndex: Profile corrupt (offset < 0)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110310	ERROR	acsStatsLocal: acsStatsLocal(%d) ERROR: cmnProfileFindIndex: Profile corrupt (offset > profileLength)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110311	ERROR	acsStatsLocal: acsStatsLocal(%d) ERROR: cmnProfileFindIndex: Profile corrupt (TOC end > profileLength)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110312	ERROR	acsStatsLocal: acsStatsLocal(%d) ERROR: cmnProfileFindTag: Profile corrupt (data pos misaligned)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110313	ERROR	acsStatsLocal: acsStatsLocal(%d) ERROR: cmnProfileFindTag: Profile corrupt (length < 0)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110314	ERROR	acsStatsLocal: acsStatsLocal(%d) ERROR: cmnProfileFindTag: Profile corrupt (offset + length > profileLength)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110315	ERROR	acsStatsLocal: acsStatsLocal(%d) ERROR: cmnProfileFindTag: Profile corrupt (offset < 0)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110316	ERROR	acsStatsLocal: acsStatsLocal(%d) ERROR: cmnProfileFindTag: Profile corrupt (offset > profileLength)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110317	ERROR	acsStatsLocal: acsStatsLocal(%d) ERROR: Remove tag: Corrupted, tag field data passes end of profile	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110318	ERROR	acsStatsLocal: acsStatsLocal(%d) ERROR: Remove tag: Corrupted, tag length begins before profile	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110319	ERROR	acsStatsLocal: acsStatsLocal(%d) ERROR: Remove tag: Corrupted, tag length field passes end of profile	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110320	ERROR	acsStatsLocal: acsStatsLocal(%d) ERROR: Update block corrupt. Item offset is negative. Creating empty block.	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110321	ERROR	acsStatsLocal: acsStatsLocal(%d) ERROR: Update block has no tags but is wrong size. Creating empty profile.	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110322	ERROR	acsStatsLocal: acsStatsLocal(%d) ERROR: Update profile corrupt. Field goes past profile block len.	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110323	ERROR	acsStatsLocal: acsStatsLocal(%d) ERROR: Update profile corrupt. Length goes past profile block len.	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110324	NOTICE	acsStatsLocal: acsStatsLocal(%d) NOTICE: gethostbyname:%z	Communications over the socket appears to have problems.	Refer to UNIX/application/LAN expert first (Check the following). 1) TCP/IP connection integrity. 2) Type netstat -na (see man netstat for more information) to determine the status of the listening socket for this connection. (Should be a configuration parameter). Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110325	NOTICE	acsStatsLocal: acsStatsLocal(%d) NOTICE: Select:%z	Communications over the socket appears to have problems.	Refer to UNIX/application/LAN expert first (Check the following). 1) TCP/IP connection integrity. 2) Type netstat -na (see man netstat for more information) to determine the status of the listening socket for this connection. (Should be a configuration parameter). Finally contact support.	ACS
110326	NOTICE	acsStatsLocal: acsStatsLocal(%d) NOTICE: socket:%z	Communications over the socket appears to have problems.	Refer to UNIX/application/LAN expert first (Check the following). 1) TCP/IP connection integrity. 2) Type netstat -na (see man netstat for more information) to determine the status of the listening socket for this connection. (Should be a configuration parameter). Finally contact support.	ACS
110327	WARNING	acsStatsLocal: acsStatsLocal(%d) WARNING: cmnPluginLookupFunction: could not find symbol %s %d::%s %d:%z	acsStatsLocal shared library is missing/corrupt.	Assuming basic UNIX skills (Check the following). 1) Check validity and permissions of the acsStatsMaster shared library in /IN/service_packages/ACS/lib. 2) Verify the entry exists for this shared library in the ACS.conf file found in /IN/service_packages/ACS/etc.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110328	WARNING	acsStatsLocal: acsStatsLocal(%d) WARNING: cmnPluginReleaseHandle: released already-released pluginZZZ	acsStatsLocal shared library is missing/corrupt.	Assuming basic UNIX skills (Check the following). 1) Check validity and permissions of the acsStatsMaster shared library in /IN/service_packages/ACS/lib. 2) Verify the entry exists for this shared library in the ACS.conf file found in /IN/service_packages/ACS/etc.	ACS
110329	WARNING	acsStatsLocal: acsStatsLocal(%d) WARNING: Macro %s %d not found.	This macro node has been encountered in a control plan but the implementation details for this macro node cannot be found.	Contact support. No further information can be obtained.	ACS
110330	ERROR	acsStatsLocal: acsStatsLocal(%d) ERROR: Could not stat() language index fileZZZ	Attempting to obtain the status of the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS
110331	ERROR	acsStatsLocal: acsStatsLocal(%d) ERROR: Could not load either the requested language file or Default.lang! Falling back to untranslated strings.	Attempting to open the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110332	ERROR	acsStatsLocal: acsStatsLocal(%d) ERROR: Could not read language index fileZZZ	Attempting to read the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS
110333	WARNING	acsStatsLocal: acsStatsLocal(%d) WARNING: cmnConfigGetStringVector: unable to openZZZ	Attempting to open the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS
110334	WARNING	acsStatsLocal: acsStatsLocal(%d) WARNING: Could not load language file %s %d! Falling back to Default.lang.	Attempting to read the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS
110335	WARNING	acsStatsLocal: acsStatsLocal(%d) WARNING: Could not reload language file %s %d! Staying with in-core copy.	Attempting to read the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110336	WARNING	acsStatsLocal: acsStatsLocal(%d) WARNING: getValue: unable to openZZZ	Attempting to read the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS
110337	WARNING	acsStatsLocal: acsStatsLocal(%d) WARNING: cmnConfigGetChar: %z	Attempting to read the acsStatsLocal configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS
110338	WARNING	acsStatsLocal: acsStatsLocal(%d) WARNING: cmnConfigGetFlag: %z	Attempting to read the acsStatsLocal configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110339	WARNING	acsStatsLocal: acsStatsLocal(%d) WARNING: cmnConfigGetInteger: %z	Attempting to read the acsStatsLocal configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS
110340	WARNING	acsStatsLocal: acsStatsLocal(%d) WARNING: cmnConfigGetString: %z	Attempting to read the acsStatsLocal configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110341	WARNING	acsStatsLocal: acsStatsLocal(%d) WARNING: getConfig: No trailing : on sectionZZZ	Attempting to read the acsStatsLocal configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS
110342	WARNING	acsStatsLocal: acsStatsLocal(%d) WARNING: Language translation dictionary in %s %d contained an invalid mapping line (no unescaped = sign) on or about line %d	Invalid line found in the currently selected language translation file.	Modify this line in the currently selected language translation file found in /IN/html/SMS/language.	ACS
110343	WARNING	acsStatsLocal: acsStatsLocal(%d) WARNING: Language string not found in currently selected language database: %s %d	Invalid line found in the currently selected language translation file.	Modify this line in the currently selected language translation file found in /IN/html/SMS/language.	ACS
110344	CRITICAL	acsStatsLocal: acsStatsLocal(%d) CRITICAL: malloc() returned NULL in build_filename (cmnLang.cc)! Out of memory!	Insufficient memory to perform desired action due to internal software error.	Refer to UNIX/application expert first (Check the following). 1) Rogue processes consuming memory 2) Unusually large memory consumption for an individual binary. Finally contact support.	ACS
110345	CRITICAL	acsStatsLocal: acsStatsLocal(%d) CRITICAL: Out of memory in cmnLang.cc:processLine!	Insufficient memory to perform desired action due to internal software error.	Refer to UNIX/application expert first (Check the following). 1) Rogue processes consuming memory 2) Unusually large memory consumption for an individual binary. Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110346	CRITICAL	acsStatsLocal: acsStatsLocal(%d) NOTICE allocate=%d cmnRangeOciFetch.c@%d: out of memory	Insufficient memory to perform desired action due to internal software error.	Refer to UNIX/application expert first (Check the following). 1) Rogue processes consuming memory 2) Unusually large memory consumption for an individual binary. Finally contact support.	ACS
110347	CRITICAL	acsStatsLocal: acsStatsLocal(%d) WARNING strdup=%d loggedError.c@%d: out of memory	Insufficient memory to perform desired action due to internal software error.	Refer to UNIX/application expert first (Check the following). 1) Rogue processes consuming memory 2) Unusually large memory consumption for an individual binary. Finally contact support.	ACS
110348	NOTICE	acsStatsLocal: acsStatsLocal(%d) NOTICE oparse=%d cmnRangeOciFetch.c@%d:%z	Cannot connect to ORACLE.	Refer to ORACLE/application expert first (Check the following). 1) Verify that ORACLE is running through checking the status of the listener(lsnrctl) and restart ORACLE only if neccessary. 2) Check the environment variables and/or configuration files: ORACLE_SID(environment), tnsnames.ora(configuration file), listener.ora(configuration file). Verify that the username and password for the current machine is correct. 3) Observe startup output for errors. Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110349	NOTICE	acsStatsLocal: acsStatsLocal(%d) NOTICE: cmnConfigGetChar: %z	Attempting to read the acsStatsLocal configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS
110350	NOTICE	acsStatsLocal: acsStatsLocal(%d) NOTICE: cmnConfigGetFlag: %z	Attempting to read the acsStatsLocal configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110351	NOTICE	acsStatsLocal: acsStatsLocal(%d) NOTICE: cmnConfigGetInteger: %z	Attempting to read the acsStatsLocal configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS
110352	NOTICE	acsStatsLocal: acsStatsLocal(%d) NOTICE: cmnConfigGetString: %z	Attempting to read the acsStatsLocal configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS
110353	ERROR	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) ERROR acsSLEEChassis_t::acsSLEEChassis_t csStatsEventCounter.cc@%d: Stats interface not found Call Dropped.	Could not retrieve SLEE Stats IF - call being dropped.	Contact support. No further information can be obtained.	ACS
110354	ERROR	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) ERROR maskSignals=%d cmnSignals.c@%d:%z	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110355	ERROR	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) ERROR unmaskSignals=%d cmnSignals.c@%d:%z	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110356	ERROR	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) ERROR: ACS Plugin %s %d returned FALSE from sharedLibraryInit	Error when trying to register this control plans feature node.	Contact support. No further information can be obtained.	ACS
110357	ERROR	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) ERROR: Could not find symbol sharedLibraryInit in ACS PluginZZZ	acsStatsLocalSLEE shared library is missing/corrupt.	Assuming basic UNIX skills (Check the following). 1) Check validity and permissions of the acsStatsLocalSLEE shared library in /IN/service_packages/ACS/lib. 2) Verify the entry exists for this shared library in the ACS.conf file found in /IN/service_packages/ACS/etc.	ACS
110358	ERROR	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) ERROR: Could not load ACS PluginZZZ	ACS Plugin shared library is missing/corrupt.	Assuming basic UNIX skills (Check the following). 1) Check validity and permissions of the ACS Plugin shared library in /IN/service_packages/ACS/lib. 2) Verify the entry exists for this shared library in the ACS.conf file found in /IN/service_packages/ACS/etc.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110359	ERROR	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) ERROR: Failed to connect to oracle as user %s %d (password hidden)	Cannot connect to ORACLE.	Refer to ORACLE/application expert first (Check the following). 1) Verify that ORACLE is running through checking the status of the listener(lsnrctl) and restart ORACLE only if neccessary. 2) Check the environment variables and/or configuration files: ORACLE_SID(environment), tnsnames.ora(configuration file), listener.ora(configuration file). Verify that the username and password for the current machine is correct. 3) Observe startup output for errors. Finally contact support.	ACS
110360	ERROR	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) ERROR: semctl() error:%z	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110361	ERROR	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) ERROR: semget() error:%z	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110362	ERROR	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) ERROR: semop() error:%z	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110363	ERROR	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) ERROR: shmat() error:%z	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110364	ERROR	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) ERROR: shmctl() error:%z	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110365	ERROR	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) ERROR: shmget() error:%z	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110366	ERROR	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) CRITICAL: Aiee! cmnPluginReleaseHandle received NULL handle!	Internal software error.	Contact support. No further information can be obtained.	ACS
110367	ERROR	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) CRITICAL: cmnPlugin: error loading library %s %d:%z	acsStatsLocalSLEE shared library is missing/corrupt.	Assuming basic UNIX skills (Check the following). 1)Check validity and permissions of the acsStatsLocalSLEE shared library in /IN/service_packages/MOB_PP/lib	ACS
110368	ERROR	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) ERROR: cmnDate::getLocalDate:%z	Internal software error.	No resolution. If problem persists then contact support.	ACS
110369	ERROR	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) ERROR: cmnProfileFindIndex: Profile corrupt (data pos misaligned)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110370	ERROR	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) ERROR: cmnProfileFindIndex: Profile corrupt (length < 0)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110371	ERROR	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) ERROR: cmnProfileFindIndex: Profile corrupt (offset + length > profileLength)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110372	ERROR	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) ERROR: cmnProfileFindIndex: Profile corrupt (offset < 0)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110373	ERROR	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) ERROR: cmnProfileFindIndex: Profile corrupt (offset > profileLength)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110374	ERROR	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) ERROR: cmnProfileFindIndex: Profile corrupt (TOC end > profileLength)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110375	ERROR	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) ERROR: cmnProfileFindTag: Profile corrupt (data pos misaligned)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110376	ERROR	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) ERROR: cmnProfileFindTag: Profile corrupt (length < 0)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110377	ERROR	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) ERROR: cmnProfileFindTag: Profile corrupt (offset + length > profileLength)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110378	ERROR	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) ERROR: cmnProfileFindTag: Profile corrupt (offset < 0)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110379	ERROR	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) ERROR: cmnProfileFindTag: Profile corrupt (offset > profileLength)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110380	ERROR	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) ERROR: Remove tag: Corrupted, tag field data passes end of profile	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110381	ERROR	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) ERROR: Remove tag: Corrupted, tag length begins before profile	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110382	ERROR	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) ERROR: Remove tag: Corrupted, tag length field passes end of profile	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110383	ERROR	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) ERROR: Update block corrupt. Item offset is negative. Creating empty block.	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110384	ERROR	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) ERROR: Update block has no tags but is wrong size. Creating empty profile.	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110385	ERROR	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) ERROR: Update profile corrupt. Field goes past profile block len.	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110386	ERROR	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) ERROR: Update profile corrupt. Length goes past profile block len.	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110387	NOTICE	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) NOTICE: gethostbyname:%z	Communications over the socket appears to have problems.	Refer to UNIX/application/LAN expert first (Check the following). 1) TCP/IP connection integrity. 2) Type netstat -na (see man netstat for more information) to determine the status of the listening socket for this connection. (Should be a configuration parameter). Finally contact support.	ACS
110388	NOTICE	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) NOTICE: Select:%z	Communications over the socket appears to have problems.	Refer to UNIX/application/LAN expert first (Check the following). 1) TCP/IP connection integrity. 2) Type netstat -na (see man netstat for more information) to determine the status of the listening socket for this connection. (Should be a configuration parameter). Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110389	NOTICE	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) NOTICE: socket:%z	Communications over the socket appears to have problems.	Refer to UNIX/application/LAN expert first (Check the following). 1) TCP/IP connection integrity. 2) Type netstat -na (see man netstat for more information) to determine the status of the listening socket for this connection. (Should be a configuration parameter). Finally contact support.	ACS
110390	WARNING	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) WARNING: cmnPluginLookupFunction: could not find symbol %s %d::%s %d:%z	acsStatsMaster shared library is missing/corrupt.	Assuming basic UNIX skills (Check the following). 1) Check validity and permissions of the acsStatsMaster shared library in /IN/service_packages/ACS/lib. 2) Verify the entry exists for this shared library in the ACS.conf file found in /IN/service_packages/ACS/etc.	ACS
110391	WARNING	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) WARNING: cmnPluginReleaseHandle: released already-released pluginZZZ	acsStatsMaster shared library is missing/corrupt.	Assuming basic UNIX skills (Check the following). 1) Check validity and permissions of the acsStatsMaster shared library in /IN/service_packages/ACS/lib. 2) Verify the entry exists for this shared library in the ACS.conf file found in /IN/service_packages/ACS/etc.	ACS
110392	WARNING	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) WARNING: Macro %s %d not found.	This macro node has been encountered in a control plan but the implementation details for this macro node cannot be found.	Contact support. No further information can be obtained.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110393	ERROR	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) ERROR: Could not stat() language index fileZZZ	Attempting to obtain the status of the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS
110394	ERROR	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) ERROR: Could not load either the requested language file or Default.lang! Falling back to untranslated strings.	Attempting to open the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS
110395	ERROR	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) ERROR: Could not read language index fileZZZ	Attempting to read the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS
110396	WARNING	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) WARNING: cmnConfigGetStringVector: unable to openZZZ	Attempting to open the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110397	WARNING	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) WARNING: Could not load language file %s %d! Falling back to Default.lang.	Attempting to read the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS
110398	WARNING	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) WARNING: Could not reload language file %s %d! Staying with in-core copy.	Attempting to read the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS
110399	WARNING	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) WARNING: getValue: unable to openZZZ	Attempting to read the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110400	WARNING	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) WARNING: cmnConfigGetChar: %z	Attempting to read the acsStatsLocalSLEE configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS
110401	WARNING	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) WARNING: cmnConfigGetFlag: %z	Attempting to read the acsStatsLocalSLEE configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110402	WARNING	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) WARNING: cmnConfigGetInteger: %z	Attempting to read the acsStatsLocalSLEE configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS
110403	WARNING	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) WARNING: cmnConfigGetString: %z	Attempting to read the acsStatsLocalSLEE configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110404	WARNING	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) WARNING: getConfig: No trailing : on sectionZZZ	Attempting to read the acsStatsLocalSLEE configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS
110405	WARNING	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) WARNING: Language translation dictionary in %s %d contained an invalid mapping line (no unescaped = sign) on or about line %d	Invalid line found in the currently selected language translation file.	Modify this line in the currently selected language translation file found in /IN/html/SMS/language.	ACS
110406	WARNING	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) WARNING: Language string not found in currently selected language database: %s %d	Invalid line found in the currently selected language translation file.	Modify this line in the currently selected language translation file found in /IN/html/SMS/language.	ACS
110407	CRITICAL	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) CRITICAL: malloc() returned NULL in build_filename (cmnLang.cc)! Out of memory!	Insufficient memory to perform desired action due to internal software error.	Refer to UNIX/application expert first (Check the following). 1) Rogue processes consuming memory 2) Unusually large memory consumption for an individual binary. Finally contact support.	ACS
110408	CRITICAL	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) CRITICAL: Out of memory in cmnLang.cc:processLine!	Insufficient memory to perform desired action due to internal software error.	Refer to UNIX/application expert first (Check the following). 1) Rogue processes consuming memory 2) Unusually large memory consumption for an individual binary. Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110409	CRITICAL	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) NOTICE allocate=%d cmnRangeOciFetch.c@%d: out of memory	Insufficient memory to perform desired action due to internal software error.	Refer to UNIX/application expert first (Check the following). 1) Rogue processes consuming memory 2) Unusually large memory consumption for an individual binary. Finally contact support.	ACS
110410	CRITICAL	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) WARNING strdup=%d loggedError.c@%d: out of memory	Insufficient memory to perform desired action due to internal software error.	Refer to UNIX/application expert first (Check the following). 1) Rogue processes consuming memory 2) Unusually large memory consumption for an individual binary. Finally contact support.	ACS
110411	NOTICE	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) NOTICE: cmnConfigGetChar: %z	Successfully read this parameter in the acsStatsLocalSLEE configuration file.	No resolution.	ACS
110412	NOTICE	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) NOTICE: cmnConfigGetFlag: %z	Successfully read this parameter in the acsStatsLocalSLEE configuration file.	No resolution.	ACS
110413	NOTICE	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) NOTICE: cmnConfigGetInteger: %z	Successfully read this parameter in the acsStatsLocalSLEE configuration file.	No resolution.	ACS
110414	NOTICE	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) NOTICE: cmnConfigGetString: %z	Successfully read this parameter in the acsStatsLocalSLEE configuration file.	No resolution.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110415	NOTICE	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) NOTICE oparse=%d cmnRangeOciFetch.c@%d:%z	Cannot connect to ORACLE.	Refer to ORACLE/application expert first (Check the following). 1) Verify that ORACLE is running through checking the status of the listener(lsnrctl) and restart ORACLE only if neccessary. 2) Check the environment variables and/or configuration files: ORACLE_SID(environment), tnsnames.ora(configuration file), listener.ora(configuration file). Verify that the username and password for the current machine is correct. 3) Observe startup output for errors. Finally contact support.	ACS
110416	ERROR	acsStatsMaster: acsStatsMaster(%d) ERROR maskSignals=%d cmnSignals.c@%d:%z	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110417	ERROR	acsStatsMaster: acsStatsMaster(%d) ERROR unmaskSignals=%d cmnSignals.c@%d:%z	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110418	ERROR	acsStatsMaster: acsStatsMaster(%d) ERROR: ACS Plugin %s %d returned FALSE from sharedLibraryInit	Error when trying to register this control plans feature node.	Contact support. No further information can be obtained.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110419	ERROR	acsStatsMaster: acsStatsMaster(%d) ERROR: bind() error:%z	Communications over the socket appears to have problems.	Refer to UNIX/application/LAN expert first (Check the following). 1) TCP/IP connection integrity. 2) Type netstat -na (see man netstat for more information) to determine the status of the listening socket for this connection. (Should be a configuration parameter). Finally contact support.	ACS
110420	ERROR	acsStatsMaster: acsStatsMaster(%d) ERROR: Could not find symbol sharedLibraryInit in ACS PluginZZZ	acsStatsMaster shared library is missing/corrupt.	Assuming basic UNIX skills (Check the following). 1) Check validity and permissions of the acsStatsMaster shared library in /IN/service_packages/ACS/lib. 2) Verify the entry exists for this shared library in the ACS.conf file found in /IN/service_packages/ACS/etc.	ACS
110421	ERROR	acsStatsMaster: acsStatsMaster(%d) ERROR: Could not load ACS PluginZZZ	ACS Plugin shared library is missing/corrupt.	Assuming basic UNIX skills (Check the following). 1) Check validity and permissions of the ACS Plugin shared library in /IN/service_packages/ACS/lib. 2) Verify the entry exists for this shared library in the ACS.conf file found in /IN/service_packages/ACS/etc.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110422	ERROR	acsStatsMaster: acsStatsMaster(%d) ERROR: Failed to connect to oracle as user %s %d (password hidden)	Cannot connect to ORACLE.	Refer to ORACLE/application expert first (Check the following). 1) Verify that ORACLE is running through checking the status of the listener(lsnrctl) and restart ORACLE only if necessary. 2) Check the environment variables and/or configuration files: ORACLE_SID(environment), tnsnames.ora(configuration file), listener.ora(configuration file). Verify that the username and password for the current machine is correct. 3) Observe startup output for errors. Finally contact support.	ACS
110423	ERROR	acsStatsMaster: acsStatsMaster(%d) ERROR: fork() error:%z	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110424	ERROR	acsStatsMaster: acsStatsMaster(%d) ERROR: listen() error:%z	Communications over the socket appears to have problems.	Refer to UNIX/application/LAN expert first (Check the following). 1) TCP/IP connection integrity. 2) Type netstat -na (see man netstat for more information) to determine the status of the listening socket for this connection. (Should be a configuration parameter). Finally contact support.	ACS
110425	ERROR	acsStatsMaster: acsStatsMaster(%d) ERROR: semctl() error:%z	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110426	ERROR	acsStatsMaster: acsStatsMaster(%d) ERROR: semget() error:%z	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110427	ERROR	acsStatsMaster: acsStatsMaster(%d) ERROR: semop() error:%z	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110428	ERROR	acsStatsMaster: acsStatsMaster(%d) ERROR: setsockopt() error:%z	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110429	ERROR	acsStatsMaster: acsStatsMaster(%d) ERROR: shmatt() error:%z	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110430	ERROR	acsStatsMaster: acsStatsMaster(%d) ERROR: shmctl() error:%z	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110431	ERROR	acsStatsMaster: acsStatsMaster(%d) ERROR: shmget() error:%z	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110432	ERROR	acsStatsMaster: acsStatsMaster(%d) ERROR: signal(), error = SIG_ERR	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110433	ERROR	acsStatsMaster: acsStatsMaster(%d) ERROR: socket() error:%z	Communications over the socket appears to have problems.	Refer to UNIX/application/LAN expert first (Check the following). 1) TCP/IP connection integrity. 2) Type netstat -na (see man netstat for more information) to determine the status of the listening socket for this connection. (Should be a configuration parameter). Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110434	WARNING	acsStatsMaster: acsStatsMaster(%d) WARNING: accept() error:%z	Communications over the socket appears to have problems.	Refer to UNIX/application/LAN expert first (Check the following). 1) TCP/IP connection integrity. 2) Type netstat -na (see man netstat for more information) to determine the status of the listening socket for this connection. (Should be a configuration parameter). Finally contact support.	ACS
110435	WARNING	acsStatsMaster: acsStatsMaster(%d) WARNING: child %d terminated	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110436	WARNING	acsStatsMaster: acsStatsMaster(%d) WARNING: close() error:%z	Communications over the socket appears to have problems.	Refer to UNIX/application/LAN expert first (Check the following). 1) TCP/IP connection integrity. 2) Type netstat -na (see man netstat for more information) to determine the status of the listening socket for this connection. (Should be a configuration parameter). Finally contact support.	ACS
110437	WARNING	acsStatsMaster: acsStatsMaster(%d) WARNING: recv() error:%z	Communications over the socket appears to have problems.	Refer to UNIX/application/LAN expert first (Check the following). 1) TCP/IP connection integrity. 2) Type netstat -na (see man netstat for more information) to determine the status of the listening socket for this connection. (Should be a configuration parameter). Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110438	WARNING	acsStatsMaster: acsStatsMaster(%d) WARNING: send() error:%z	Communications over the socket appears to have problems.	Refer to UNIX/application/LAN expert first (Check the following). 1) TCP/IP connection integrity. 2) Type netstat -na (see man netstat for more information) to determine the status of the listening socket for this connection. (Should be a configuration parameter). Finally contact support.	ACS
110439	ERROR	acsStatsMaster: acsStatsMaster(%d) CRITICAL: Aieee! cmnPluginReleaseHandle received NULL handle!	Internal software error.	Contact support. No further information can be obtained.	ACS
110440	ERROR	acsStatsMaster: acsStatsMaster(%d) CRITICAL: cmnPlugin: error loading library %s %d:%z	acsStatsMaster shared library is missing/corrupt.	Assuming basic UNIX skills (Check the following). 1) Check validity and permissions of the acsStatsMaster shared library in /IN/service_packages/MOB_PP/lib	ACS
110441	ERROR	acsStatsMaster: acsStatsMaster(%d) ERROR: cmnDate::getLocalDate:%z	Internal software error.	No resolution. If problem persists then contact support.	ACS
110442	ERROR	acsStatsMaster: acsStatsMaster(%d) ERROR: cmnProfileFindIndex: Profile corrupt (data pos misaligned)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110443	ERROR	acsStatsMaster: acsStatsMaster(%d) ERROR: cmnProfileFindIndex: Profile corrupt (length < 0)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110444	ERROR	acsStatsMaster: acsStatsMaster(%d) ERROR: cmnProfileFindIndex: Profile corrupt (offset + length > profileLength)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110445	ERROR	acsStatsMaster: acsStatsMaster(%d) ERROR: cmnProfileFindIndex: Profile corrupt (offset < 0)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110446	ERROR	acsStatsMaster: acsStatsMaster(%d) ERROR: cmnProfileFindIndex: Profile corrupt (offset > profileLength)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110447	ERROR	acsStatsMaster: acsStatsMaster(%d) ERROR: cmnProfileFindIndex: Profile corrupt (TOC end > profileLength)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110448	ERROR	acsStatsMaster: acsStatsMaster(%d) ERROR: cmnProfileFindTag: Profile corrupt (data pos misaligned)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110449	ERROR	acsStatsMaster: acsStatsMaster(%d) ERROR: cmnProfileFindTag: Profile corrupt (length < 0)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110450	ERROR	acsStatsMaster: acsStatsMaster(%d) ERROR: cmnProfileFindTag: Profile corrupt (offset + length > profileLength)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110451	ERROR	acsStatsMaster: acsStatsMaster(%d) ERROR: cmnProfileFindTag: Profile corrupt (offset < 0)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110452	ERROR	acsStatsMaster: acsStatsMaster(%d) ERROR: cmnProfileFindTag: Profile corrupt (offset > profileLength)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110453	ERROR	acsStatsMaster: acsStatsMaster(%d) ERROR: Remove tag: Corrupted, tag field data passes end of profile	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110454	ERROR	acsStatsMaster: acsStatsMaster(%d) ERROR: Remove tag: Corrupted, tag length begins before profile	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110455	ERROR	acsStatsMaster: acsStatsMaster(%d) ERROR: Remove tag: Corrupted, tag length field passes end of profile	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110456	ERROR	acsStatsMaster: acsStatsMaster(%d) ERROR: Update block corrupt. Item offset is negative. Creating empty block.	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110457	ERROR	acsStatsMaster: acsStatsMaster(%d) ERROR: Update block has no tags but is wrong size. Creating empty profile.	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110458	ERROR	acsStatsMaster: acsStatsMaster(%d) ERROR: Update profile corrupt. Field goes past profile block len.	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110459	ERROR	acsStatsMaster: acsStatsMaster(%d) ERROR: Update profile corrupt. Length goes past profile block len.	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110460	NOTICE	acsStatsMaster: acsStatsMaster(%d) NOTICE: gethostbyname:%z	Communications over the socket appears to have problems.	Refer to UNIX/application/LAN expert first (Check the following). 1) TCP/IP connection integrity. 2) Type netstat -na (see man netstat for more information) to determine the status of the listening socket for this connection. (Should be a configuration parameter). Finally contact support.	ACS
110461	NOTICE	acsStatsMaster: acsStatsMaster(%d) NOTICE: Select:%z	Communications over the socket appears to have problems.	Refer to UNIX/application/LAN expert first (Check the following). 1) TCP/IP connection integrity. 2) Type netstat -na (see man netstat for more information) to determine the status of the listening socket for this connection. (Should be a configuration parameter). Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110462	NOTICE	acsStatsMaster: acsStatsMaster(%d) NOTICE: socket:%z	Communications over the socket appears to have problems.	Refer to UNIX/application/LAN expert first (Check the following). 1) TCP/IP connection integrity. 2) Type netstat -na (see man netstat for more information) to determine the status of the listening socket for this connection. (Should be a configuration parameter). Finally contact support.	ACS
110463	WARNING	acsStatsMaster: acsStatsMaster(%d) WARNING: cmnPluginLookupFunction: could not find symbol %s %d::%s %d:%z	acsStatsMaster shared library is missing/corrupt.	Assuming basic UNIX skills (Check the following). 1) Check validity and permissions of the acsStatsMaster shared library in /IN/service_packages/ACS/lib. 2) Verify the entry exists for this shared library in the ACS.conf file found in /IN/service_packages/ACS/etc.	ACS
110464	WARNING	acsStatsMaster: acsStatsMaster(%d) WARNING: cmnPluginReleaseHandle: released already-released pluginZZZ	acsStatsMaster shared library is missing/corrupt.	Assuming basic UNIX skills (Check the following). 1) Check validity and permissions of the acsStatsMaster shared library in /IN/service_packages/ACS/lib. 2) Verify the entry exists for this shared library in the ACS.conf file found in /IN/service_packages/ACS/etc.	ACS
110465	WARNING	acsStatsMaster: acsStatsMaster(%d) WARNING: Macro %s %d not found.	This macro node has been encountered in a control plan but the implementation details for this macro node cannot be found.	Contact support. No further information can be obtained.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110466	ERROR	acsStatsMaster: acsStatsMaster(%d) ERROR: Could not stat() language index fileZZZ	Attempting to obtain the status of the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS
110467	ERROR	acsStatsMaster: acsStatsMaster(%d) ERROR: Could not load either the requested language file or Default.lang! Falling back to untranslated strings.	Attempting to open the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS
110468	ERROR	acsStatsMaster: acsStatsMaster(%d) ERROR: Could not read language index fileZZZ	Attempting to read the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS
110469	WARNING	acsStatsMaster: acsStatsMaster(%d) WARNING: cmnConfigGetStringVector: unable to openZZZ	Attempting to open the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110470	WARNING	acsStatsMaster: acsStatsMaster(%d) WARNING: Could not load language file %s %d! Falling back to Default.lang.	Attempting to read the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS
110471	WARNING	acsStatsMaster: acsStatsMaster(%d) WARNING: Could not reload language file %s %d! Staying with in-core copy.	Attempting to read the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS
110472	WARNING	acsStatsMaster: acsStatsMaster(%d) WARNING: getValue: unable to openZZZ	Attempting to read the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110473	WARNING	acsStatsMaster: acsStatsMaster(%d) WARNING: cmnConfigGetChar: %z	Attempting to read the acsStatsMaster configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS
110474	WARNING	acsStatsMaster: acsStatsMaster(%d) WARNING: cmnConfigGetFlag: %z	Attempting to read the acsStatsMaster configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110475	WARNING	acsStatsMaster: acsStatsMaster(%d) WARNING: cmnConfigGetInteger: %z	Attempting to read the acsStatsMaster configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS
110476	WARNING	acsStatsMaster: acsStatsMaster(%d) WARNING: cmnConfigGetString: %z	Attempting to read the acsStatsMaster configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110477	WARNING	acsStatsMaster: acsStatsMaster(%d) WARNING: getConfig: No trailing : on sectionZZZ	Attempting to read the acsStatsMaster configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS
110478	WARNING	acsStatsMaster: acsStatsMaster(%d) WARNING: Language translation dictionary in %s %d contained an invalid mapping line (no unescaped = sign) on or about line %d	Invalid line found in the currently selected language translation file.	Modify this line in the currently selected language translation file found in /IN/html/SMS/language.	ACS
110479	WARNING	acsStatsMaster: acsStatsMaster(%d) WARNING: Language string not found in currently selected language database: %s %d	Invalid line found in the currently selected language translation file.	Modify this line in the currently selected language translation file found in /IN/html/SMS/language.	ACS
110480	CRITICAL	acsStatsMaster: acsStatsMaster(%d) CRITICAL: malloc() returned NULL in build_filename (cmnLang.cc)! Out of memory!	Insufficient memory to perform desired action due to internal software error.	Refer to UNIX/application expert first (Check the following). 1) Rogue processes consuming memory 2) Unusually large memory consumption for an individual binary. Finally contact support.	ACS
110481	CRITICAL	acsStatsMaster: acsStatsMaster(%d) CRITICAL: Out of memory in cmnLang.cc:processLine!	Insufficient memory to perform desired action due to internal software error.	Refer to UNIX/application expert first (Check the following). 1) Rogue processes consuming memory 2) Unusually large memory consumption for an individual binary. Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110482	CRITICAL	acsStatsMaster: acsStatsMaster(%d) NOTICE allocate=%d cmnRangeOciFetch.c@%d: out of memory	Insufficient memory to perform desired action due to internal software error.	Refer to UNIX/application expert first (Check the following). 1) Rogue processes consuming memory 2) Unusually large memory consumption for an individual binary. Finally contact support.	ACS
110483	CRITICAL	acsStatsMaster: acsStatsMaster(%d) WARNING strdup=%d loggedError.c@%d: out of memory	Insufficient memory to perform desired action due to internal software error.	Refer to UNIX/application expert first (Check the following). 1) Rogue processes consuming memory 2) Unusually large memory consumption for an individual binary. Finally contact support.	ACS
110484	NOTICE	acsStatsMaster: acsStatsMaster(%d) NOTICE: ***AcsStatsMaster Shutdown***	Informational alarm - acsStatsMaster successfully shutdown.	No resolution.	ACS
110485	NOTICE	acsStatsMaster: acsStatsMaster(%d) NOTICE: ***Startup Successfull***	Informational alarm - acsStatsMaster successfully started.	No resolution.	ACS
110486	NOTICE	acsStatsMaster: acsStatsMaster(%d) NOTICE: Running acsStatsMaster as a daemon server	Informational alarm - acsStatsMaster has started successfully.	No resolution.	ACS
110487	NOTICE	acsStatsMaster: acsStatsMaster(%d) NOTICE: cmnConfigGetChar: %z	Successfully read this parameter in the acsStatsMaster configuration file.	No resolution.	ACS
110488	NOTICE	acsStatsMaster: acsStatsMaster(%d) NOTICE: cmnConfigGetFlag: %z	Successfully read this parameter in the acsStatsMaster configuration file.	No resolution.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110489	NOTICE	acsStatsMaster: acsStatsMaster(%d) NOTICE: cmnConfigGetInteger: %z	Successfully read this parameter in the acsStatsMaster configuration file.	No resolution.	ACS
110490	NOTICE	acsStatsMaster: acsStatsMaster(%d) NOTICE: cmnConfigGetString: %z	Successfully read this parameter in the acsStatsMaster configuration file.	No resolution.	ACS
110491	NOTICE	acsStatsMaster: acsStatsMaster(%d) NOTICE oparse=%d cmnRangeOciFetch.c@%d:%z	Cannot connect to ORACLE.	Refer to ORACLE/application expert first (Check the following). 1) Verify that ORACLE is running through checking the status of the listener(lsnrctl) and restart ORACLE only if neccessary. 2) Check the environment variables and/or configuration files: ORACLE_SID(environment), tnsnames.ora(configuration file), listener.ora(configuration file). Verify that the username and password for the current machine is correct. 3) Observe startup output for errors. Finally contact support.	ACS
110492	NOTICE	acsStatsMaster: acsStatsMaster(%d) NOTICE: PID of acsStatsMaster daemon - %d	Informational alarm - acsStatsMaster has started successfully.	No resolution.	ACS
110493	NOTICE	acsStatsMaster: acsStatsMaster(%d) NOTICE: Unknown client request type = %d	acsStatsMaster received an unknown client request type	No resolution.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110494	ERROR	acsTZCompiler: acsTZCompiler(%d) ERROR main=%d acsTZCompiler.cc@%d: Unable to connect to Oracle	Cannot connect to ORACLE.	Refer to ORACLE/application expert first (Check the following). 1) Verify that ORACLE is running through checking the status of the listener(lsnrctl) and restart ORACLE only if necessary. 2) Check the environment variables and/or configuration files: ORACLE_SID(environment), tnsnames.ora(configuration file), listener.ora(configuration file). Verify that the username and password for the current machine is correct. 3) Observe startup output for errors. Finally contact support.	ACS
110495	ERROR	acsTZCompiler: acsTZCompiler(%d) ERROR maskSignals=%d cmnSignals.c@%d:%z	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110496	ERROR	acsTZCompiler: acsTZCompiler(%d) ERROR unmaskSignals=%d cmnSignals.c@%d:%z	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110497	ERROR	acsTZCompiler: acsTZCompiler(%d) ERROR: ACS Plugin %s %d returned FALSE from sharedLibraryInit	Error when trying to register this control plans feature node.	Contact support. No further information can be obtained.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110498	ERROR	acsTZCompiler: acsTZCompiler(%d) ERROR: Could not find symbol sharedLibraryInit in ACS PluginZZZ	acsTZCompiler shared library is missing/corrupt.	Assuming basic UNIX skills (Check the following). 1)Check validity and permissions of the acsTZCompiler shared library in /IN/service_packages/ACS/lib. 2) Verify the entry exists for this shared library in the ACS.conf file found in /IN/service_packages/ACS/etc.	ACS
110499	ERROR	acsTZCompiler: acsTZCompiler(%d) ERROR: Could not load ACS PluginZZZ	ACS Plugin shared library is missing/corrupt.	Assuming basic UNIX skills (Check the following). 1)Check validity and permissions of the ACS Plugin shared library in /IN/service_packages/ACS/lib. 2) Verify the entry exists for this shared library in the ACS.conf file found in /IN/service_packages/ACS/etc.	ACS
110500	ERROR	acsTZCompiler: acsTZCompiler(%d) ERROR: Failed to connect to oracle as user %s %d (password hidden)	Cannot connect to ORACLE.	Refer to ORACLE/application expert first (Check the following). 1)Verify that ORACLE is running through checking the status of the listener(lsnrctl) and restart ORACLE only if neccessary. 2) Check the environment variables and/or configuration files: ORACLE_SID(environment), tnsnames.ora(configuration file), listener.ora(configuration file). Verify that the username and password for the current machine is correct. 3) Observe startup output for errors. Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110501	ERROR	acsTZCompiler: acsTZCompiler(%d) CRITICAL: Aiee! cmnPluginReleaseHandle received NULL handle!	Internal software error.	Contact support. No further information can be obtained.	ACS
110502	ERROR	acsTZCompiler: acsTZCompiler(%d) CRITICAL: cmnPlugin: error loading library %s %d:%z	acsStatsMaster shared library is missing/corrupt.	Assuming basic UNIX skills (Check the following). 1)Check validity and permissions of the acsStatsMaster shared library in /IN/service_packages/MOB_PP/lib	ACS
110503	ERROR	acsTZCompiler: acsTZCompiler(%d) ERROR: cmnDate::getLocalDate:%z	Internal software error.	No resolution. If problem persists then contact support.	ACS
110504	ERROR	acsTZCompiler: acsTZCompiler(%d) ERROR: cmnProfileFindIndex: Profile corrupt (data pos misaligned)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110505	ERROR	acsTZCompiler: acsTZCompiler(%d) ERROR: cmnProfileFindIndex: Profile corrupt (length < 0)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110506	ERROR	acsTZCompiler: acsTZCompiler(%d) ERROR: cmnProfileFindIndex: Profile corrupt (offset + length > profileLength)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110507	ERROR	acsTZCompiler: acsTZCompiler(%d) ERROR: cmnProfileFindIndex: Profile corrupt (offset < 0)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110508	ERROR	acsTZCompiler: acsTZCompiler(%d) ERROR: cmnProfileFindIndex: Profile corrupt (offset > profileLength)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110509	ERROR	acsTZCompiler: acsTZCompiler(%d) ERROR: cmnProfileFindIndex: Profile corrupt (TOC end > profileLength)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110510	ERROR	acsTZCompiler: acsTZCompiler(%d) ERROR: cmnProfileFindTag: Profile corrupt (data pos misaligned)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110511	ERROR	acsTZCompiler: acsTZCompiler(%d) ERROR: cmnProfileFindTag: Profile corrupt (length < 0)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110512	ERROR	acsTZCompiler: acsTZCompiler(%d) ERROR: cmnProfileFindTag: Profile corrupt (offset + length > profileLength)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110513	ERROR	acsTZCompiler: acsTZCompiler(%d) ERROR: cmnProfileFindTag: Profile corrupt (offset < 0)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110514	ERROR	acsTZCompiler: acsTZCompiler(%d) ERROR: cmnProfileFindTag: Profile corrupt (offset > profileLength)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110515	ERROR	acsTZCompiler: acsTZCompiler(%d) ERROR: Remove tag: Corrupted, tag field data passes end of profile	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110516	ERROR	acsTZCompiler: acsTZCompiler(%d) ERROR: Remove tag: Corrupted, tag length begins before profile	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110517	ERROR	acsTZCompiler: acsTZCompiler(%d) ERROR: Remove tag: Corrupted, tag length field passes end of profile	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110518	ERROR	acsTZCompiler: acsTZCompiler(%d) ERROR: Update block corrupt. Item offset is negative. Creating empty block.	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110519	ERROR	acsTZCompiler: acsTZCompiler(%d) ERROR: Update block has no tags but is wrong size. Creating empty profile.	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110520	ERROR	acsTZCompiler: acsTZCompiler(%d) ERROR: Update profile corrupt. Field goes past profile block len.	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110521	ERROR	acsTZCompiler: acsTZCompiler(%d) ERROR: Update profile corrupt. Length goes past profile block len.	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110522	NOTICE	acstZCompiler: acstZCompiler(%d) NOTICE: gethostbyname:%z	Communications over the socket appears to have problems.	Refer to UNIX/application/LAN expert first (Check the following). 1) TCP/IP connection integrity. 2) Type netstat -na (see man netstat for more information) to determine the status of the listening socket for this connection. (Should be a configuration parameter). Finally contact support.	ACS
110523	NOTICE	acstZCompiler: acstZCompiler(%d) NOTICE: Select:%z	Communications over the socket appears to have problems.	Refer to UNIX/application/LAN expert first (Check the following). 1) TCP/IP connection integrity. 2) Type netstat -na (see man netstat for more information) to determine the status of the listening socket for this connection. (Should be a configuration parameter). Finally contact support.	ACS
110524	NOTICE	acstZCompiler: acstZCompiler(%d) NOTICE: socket:%z	Communications over the socket appears to have problems.	Refer to UNIX/application/LAN expert first (Check the following). 1) TCP/IP connection integrity. 2) Type netstat -na (see man netstat for more information) to determine the status of the listening socket for this connection. (Should be a configuration parameter). Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110525	WARNING	acsTZCompiler: acsTZCompiler(%d) WARNING: cmnPluginLookupFunction: could not find symbol %s %d::%s %d:%z	acsStatsMaster shared library is missing/corrupt.	Assuming basic UNIX skills (Check the following). 1) Check validity and permissions of the acsStatsMaster shared library in /IN/service_packages/ACS/lib. 2) Verify the entry exists for this shared library in the ACS.conf file found in /IN/service_packages/ACS/etc.	ACS
110526	WARNING	acsTZCompiler: acsTZCompiler(%d) WARNING: cmnPluginReleaseHandle: released already-released pluginZZZ	acsStatsMaster shared library is missing/corrupt.	Assuming basic UNIX skills (Check the following). 1) Check validity and permissions of the acsStatsMaster shared library in /IN/service_packages/ACS/lib. 2) Verify the entry exists for this shared library in the ACS.conf file found in /IN/service_packages/ACS/etc.	ACS
110527	WARNING	acsTZCompiler: acsTZCompiler(%d) WARNING: Macro %s %d not found.	This macro node has been encountered in a control plan but the implementation details for this macro node cannot be found.	Contact support. No further information can be obtained.	ACS
110528	ERROR	acsTZCompiler: acsTZCompiler(%d) ERROR: Could not stat() language index fileZZZ	Attempting to obtain the status of the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110529	ERROR	acsTZCompiler: acsTZCompiler(%d) ERROR: Could not load either the requested language file or Default.lang! Falling back to untranslated strings.	Attempting to open the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS
110530	ERROR	acsTZCompiler: acsTZCompiler(%d) ERROR: Could not read language index fileZZZ	Attempting to read the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS
110531	WARNING	acsTZCompiler: acsTZCompiler(%d) WARNING: cmnConfigGetStringVector: unable to openZZZ	Attempting to open the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS
110532	WARNING	acsTZCompiler: acsTZCompiler(%d) WARNING: Could not load language file %s %d! Falling back to Default.lang.	Attempting to read the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110533	WARNING	acsTZCompiler: acsTZCompiler(%d) WARNING: Could not reload language file %s %d! Staying with in-core copy.	Attempting to read the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS
110534	WARNING	acsTZCompiler: acsTZCompiler(%d) WARNING: getValue: unable to openZZZ	Attempting to read the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS
110535	WARNING	acsTZCompiler: acsTZCompiler(%d) WARNING: cmnConfigGetChar: %z	Attempting to read the acsStatsMaster configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110536	WARNING	acsTZCompiler: acsTZCompiler(%d) WARNING: cmnConfigGetFlag: %z	Attempting to read the acsStatsMaster configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS
110537	WARNING	acsTZCompiler: acsTZCompiler(%d) WARNING: cmnConfigGetInteger: %z	Attempting to read the acsStatsMaster configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110538	WARNING	acsTZCompiler: acsTZCompiler(%d) WARNING: cmnConfigGetString: %z	Attempting to read the acsStatsMaster configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS
110539	WARNING	acsTZCompiler: acsTZCompiler(%d) WARNING: getConfig: No trailing : on sectionZZZ	Attempting to read the acsStatsMaster configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS
110540	WARNING	acsTZCompiler: acsTZCompiler(%d) WARNING: Language translation dictionary in %s %d contained an invalid mapping line (no unescaped = sign) on or about line %d	Invalid line found in the currently selected language translation file.	Modify this line in the currently selected language translation file found in /IN/html/SMS/language.	ACS
110541	WARNING	acsTZCompiler: acsTZCompiler(%d) WARNING: Language string not found in currently selected language database: %s %d	Invalid line found in the currently selected language translation file.	Modify this line in the currently selected language translation file found in /IN/html/SMS/language.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110542	CRITICAL	acsTZCompiler: acsTZCompiler(%d) CRITICAL: malloc() returned NULL in build_filename (cmnLang.cc)! Out of memory!	Insufficient memory to perform desired action due to internal software error.	Refer to UNIX/application expert first (Check the following). 1) Rogue processes consuming memory 2) Unusually large memory consumption for an individual binary. Finally contact support.	ACS
110543	CRITICAL	acsTZCompiler: acsTZCompiler(%d) CRITICAL: Out of memory in cmnLang.cc:processLine!	Insufficient memory to perform desired action due to internal software error.	Refer to UNIX/application expert first (Check the following). 1) Rogue processes consuming memory 2) Unusually large memory consumption for an individual binary. Finally contact support.	ACS
110544	CRITICAL	acsTZCompiler: acsTZCompiler(%d) NOTICE allocate=%d cmnRangeOciFetch.c@%d: out of memory	Insufficient memory to perform desired action due to internal software error.	Refer to UNIX/application expert first (Check the following). 1) Rogue processes consuming memory 2) Unusually large memory consumption for an individual binary. Finally contact support.	ACS
110545	CRITICAL	acsTZCompiler: acsTZCompiler(%d) WARNING strdup=%d loggedError.c@%d: out of memory	Insufficient memory to perform desired action due to internal software error.	Refer to UNIX/application expert first (Check the following). 1) Rogue processes consuming memory 2) Unusually large memory consumption for an individual binary. Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110546	NOTICE	acsTZCompiler: acsTZCompiler(%d) NOTICE oparse=%d cmnRangeOciFetch.c@%d:%z	Cannot connect to ORACLE.	Refer to ORACLE/application expert first (Check the following). 1) Verify that ORACLE is running through checking the status of the listener(lsnrctl) and restart ORACLE only if neccessary. 2) Check the environment variables and/or configuration files: ORACLE_SID(environment), tnsnames.ora(configuration file), listener.ora(configuration file). Verify that the username and password for the current machine is correct. 3) Observe startup output for errors. Finally contact support.	ACS
110547	NOTICE	acsTZCompiler: acsTZCompiler(%d) NOTICE: cmnConfigGetChar: %z	Successfully read this parameter in the acsStatsLocalSLEE configuration file.	No resolution.	ACS
110548	NOTICE	acsTZCompiler: acsTZCompiler(%d) NOTICE: cmnConfigGetFlag: %z	Successfully read this parameter in the acsStatsLocalSLEE configuration file.	No resolution.	ACS
110549	NOTICE	acsTZCompiler: acsTZCompiler(%d) NOTICE: cmnConfigGetInteger: %z	Successfully read this parameter in the acsStatsLocalSLEE configuration file.	No resolution.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110550	NOTICE	acsTZCompiler: acsTZCompiler(%d) NOTICE: cmnConfigGetString: %z	Successfully read this parameter in the acsStatsLocalSLEE configuration file.	No resolution.	ACS
110551	ERROR	SLEE[%d]: slee_acs(%d) ERROR acsChassisServiceSetup=%d acsChassisService.c@%d: Configuration File error. Problem with Shared Library	The ACS.conf file is missing a ServiceEntry parameter.	Refer to application expert. Verify that all the necessary parameters exist in the ACS.conf file found in /IN/service_packages/ACS/etc. If unsure of configuration details then contact support.	ACS
110552	ERROR	SLEE[%d]: slee_acs(%d) ERROR acsChassisServiceSetup=%d acsChassisService.c@%d: Configuration File error. Shared Library Initialization Error	The ACS.conf file is missing a ServiceEntry parameter.	Refer to application expert. Verify that all the necessary parameters exist in the ACS.conf file found in /IN/service_packages/ACS/etc. If unsure of configuration details then contact support.	ACS
110553	ERROR	SLEE[%d]: slee_acs(%d) ERROR acsChassisServiceSetup=%d acsChassisService.c@%d: Configuration File error. Unknown Chassis Type	The ACS.conf file is missing a ServiceEntry parameter.	Refer to application expert. Verify that all the necessary parameters exist in the ACS.conf file found in /IN/service_packages/ACS/etc. If unsure of configuration details then contact support.	ACS
110554	ERROR	SLEE[%d]: slee_acs(%d) ERROR acsChassisSetupCDR=%d acsChassisCDR.c@%d: Unable to configure CDR subsystem	The ACS.conf file is missing a chassis parameter needed for configuring the CDR subsystem.	Refer to application expert. Verify that all the necessary parameters exist in the ACS.conf file found in /IN/service_packages/ACS/etc. If unsure of configuration details then contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110555	ERROR	SLEE[%d]: slee_acs(%d) ERROR acsChassisSetupEmergencyNumbers= %d acsChassisEmergency.cc@%d: Configuration File error.	The ACS.conf file is missing a chassis parameter needed for configuring the emergency numbers.	Refer to application expert. Verify that all the necessary parameters exist in the ACS.conf file found in /IN/service_packages/ACS/etc. If unsure of configuration details then contact support.	ACS
110556	ERROR	SLEE[%d]: slee_acs(%d) ERROR acsParseServiceLine=%d acsChassis.cc@%d: Configuration File error. Misformatted SLEE String	The ACS.conf file contains an invalid parameter.	Refer to application expert. Verify that all the necessary parameters exist in the ACS.conf file found in /IN/service_packages/ACS/etc. If unsure of configuration details then contact support.	ACS
110557	ERROR	SLEE[%d]: slee_acs(%d) ERROR acsSLEEChassis_t::acsSLEEChassis _t=%d acsChassis.cc@%d: Configuration File error. Chassis failed setup	The ACS.conf file contains an invalid parameter.	Refer to application expert. Verify that all the necessary parameters exist in the ACS.conf file found in /IN/service_packages/ACS/etc. If unsure of configuration details then contact support.	ACS
110558	ERROR	SLEE[%d]: slee_acs(%d) ERROR activateACSCallPlan=%d acsChassisDB.pc@%d:%z	Cannot find this control plan in the ACS_CALL_PLAN(public synonym) table.	Refer to application expert. Verify that this control plan exists - name field of ACS_CALL_PLAN(public synonym) table. If unsure of control plan details then contact support	ACS
110559	ERROR	SLEE[%d]: slee_acs(%d) ERROR findMidCallReturnCallPlan=%d acsChassisDB.pc@%d:%z	Cannot find this control plan in the ACS_CALL_PLAN(public synonym) table.	Refer to application expert. Verify that this control plan exists - name field of ACS_CALL_PLAN(public synonym) table. If unsure of control plan details then contact support	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110560	ERROR	SLEE[%d]: slee_acs(%d) ERROR acsSLEEChassis_t::=%d acsChassisTelephony.cc@%d: Event received for non-existent call.	ACS Chassis received an event for an unknown call.	Contact support.	ACS
110561	ERROR	SLEE[%d]: slee_acs(%d) ERROR acsSLEEChassis_t::applyCharging= %d acsChassisTelephony.cc@%d: Event received for non-existent call.	ACS Chassis received an event for an unknown call - cannot send an Aplly Charging message for this unknown call.	Contact support.	ACS
110562	ERROR	SLEE[%d]: slee_acs(%d) ERROR acsSLEEChassis_t::attemptTermina tion=%d acsChassisTelephony.cc@%d: Event received for non-existent call.	ACS Chassis received an event for an unknown call - attempting to connect the call to the specified number has failed.	Contact support.	ACS
110563	ERROR	SLEE[%d]: slee_acs(%d) ERROR acsSLEEChassis_t::clearLeg1BCSMT triggers=%d acsChassisTelephony.cc@%d: Event received for non-existent call.	ACS Chassis received an event for an unknown call - cannot clear the Basic Call State Model triggers on this leg for this unknown call.	Contact support.	ACS
110564	ERROR	SLEE[%d]: slee_acs(%d) ERROR acsSLEEChassis_t::clearNoAnswerB CSMTriggers=%d acsChassisTelephony.cc@%d: Event received for non-existent call.	ACS Chassis received an event for an unknown call - cannot clear the Basic Call State Model triggers on this non-invoked leg for this unknown call.	Contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110565	ERROR	SLEE[%d]: slee_acs(%d) ERROR acsSLEEChassis_t::disconnectCall =%d acsChassisTelephony.cc@%d: Event received for non-existent call.	ACS Chassis received an event for an unknown call - cannot place a Release Call action for this unknown call.	Contact support.	ACS
110566	ERROR	SLEE[%d]: slee_acs(%d) ERROR acsSLEEChassis_t::enqueueCallInf ormationRequest=%d acsChassisTelephony.cc@%d: Event received for non-existent call.	ACS Chassis received an event for an unknown call - cannot add Call Information Request to the TCAP primitive list.	Contact support.	ACS
110567	ERROR	SLEE[%d]: slee_acs(%d) ERROR acsSLEEChassis_t::handleAbort=%d acsChassisTelephony.cc@%d: Event received for non-existent call.	ACS Chassis received an event for an unknown call - cannot handle the incoming Abort message for this unknown call.	Contact support.	ACS
110568	ERROR	SLEE[%d]: slee_acs(%d) ERROR acsSLEEChassis_t::handleACR=%d acsChassisTelephony.cc@%d: Event received for non-existent call.	ACS Chassis received an event for an unknown call - cannot handle the incoming Apply Charging Reports for this unknown call.	Contact support.	ACS
110569	ERROR	SLEE[%d]: slee_acs(%d) ERROR acsSLEEChassis_t::handleARI=%d acsChassisTelephony.cc@%d: Event received for non-existent call.	ACS Chassis received an event for an unknown call - cannot handle the incoming Assist Request Instructions for this unknown call.	Contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110570	ERROR	SLEE[%d]: slee_acs(%d) ERROR acsSLEEChassis_t::handleBCSMEven t=%d acsChassisTelephony.cc@%d: Event received for non-existent call.	ACS Chassis received an event for an unknown call - cannot handle the incoming Basic Call State Model event for the unknown call.	Contact support.	ACS
110571	ERROR	SLEE[%d]: slee_acs(%d) ERROR acsSLEEChassis_t::handleCIR=%d acsChassisTelephony.cc@%d: Event received for non-existent call.	ACS Chassis received an event for an unknown call - cannot handle the incoming Call Information Report for this unknown call.	Contact support.	ACS
110572	ERROR	SLEE[%d]: slee_acs(%d) ERROR acsSLEEChassis_t::handleConnectE rror=%d acsChassisTelephony.cc@%d: Event received for non-existent call.	ACS Chassis received an event for an unknown call - cannot handle the incoming Connect Errors for this unknown call.	Contact support.	ACS
110573	ERROR	SLEE[%d]: slee_acs(%d) ERROR acsSLEEChassis_t::handleContinue Error=%d acsChassisTelephony.cc@%d: Event received for non-existent call.	ACS Chassis received an event for an unknown call - cannot handle the incoming Continue Errors for this unknown call.	Contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110574	ERROR	SLEE[%d]: slee_acs(%d) ERROR acsSLEEChassis_t::handleCTRError= = %d acsChassisTelephony.cc@%d: Event received for non-existent call.	ACS Chassis received an event for an unknown call - cannot handle the incoming Connect To Resource Errors for this unknown call.	Contact support.	ACS
110575	ERROR	SLEE[%d]: slee_acs(%d) ERROR acsSLEEChassis_t::handleETCError= = %d acsChassisTelephony.cc@%d: Event received for non-existent call.	ACS Chassis received an event for an unknown call - cannot handle the incoming Establish Temporary Connection Errors for this unknown call.	Contact support.	ACS
110576	ERROR	SLEE[%d]: slee_acs(%d) ERROR acsSLEEChassis_t::handlePAError= = %d acsChassisTelephony.cc@%d: Event received for non-existent call.	ACS Chassis received an event for an unknown call - cannot handle the incoming Play Announcement Errors for this unknown call.	Contact support.	ACS
110577	ERROR	SLEE[%d]: slee_acs(%d) ERROR acsSLEEChassis_t::handlePCUIError= = %d acsChassisTelephony.cc@%d: Event received for non-existent call.	ACS Chassis received an event for an unknown call - cannot handle the incoming Prompt and Collect User Information Errors for this unknown call.	Contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110578	ERROR	SLEE[%d]: slee_acs(%d) ERROR acsSLEEChassis_t::handlePCUIResult=%d acsChassisTelephony.cc@%d: Event received for non-existent call.	ACS Chassis received an event for an unknown call - cannot handle the incoming Prompt and Collect User Information Result for this unknown call.	Contact support.	ACS
110579	ERROR	SLEE[%d]: slee_acs(%d) ERROR acsSLEEChassis_t::handleRRBCSMError=%d acsChassisTelephony.cc@%d: Event received for non-existent call.	ACS Chassis received an event for an unknown call - cannot handle the Request Report Basic Call State Model Errors for this unknown call.	Contact support.	ACS
110580	ERROR	SLEE[%d]: slee_acs(%d) ERROR acsSLEEChassis_t::handleSRR=%d acsChassisTelephony.cc@%d: Event received for non-existent call.	ACS Chassis received an event for an unknown call - cannot handle the incoming Specialised Resource Report for this unknown call.	Contact support.	ACS
110581	ERROR	SLEE[%d]: slee_acs(%d) ERROR acsSLEEChassis_t::handleStatsReplyMessage=%d acsChassisStats.cc@%d: Event received for non-existent call.	ACS Chassis received a reply message to decode for an unknown call.	Contact support.	ACS
110582	ERROR	SLEE[%d]: slee_acs(%d) ERROR acsSLEEChassis_t::terminateCall=%d acsChassisTelephony.cc@%d: Event received for non-existent call.	ACS Chassis received an event for an unknown call - attempting to connect the call to the specified number has failed.	Contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110583	ERROR	SLEE[%d]: slee_acs(%d) ERROR acsSLEEChassis_t::callEngine=%d acsChassis.cc@%d: Engine error. Run-time error in engine. dropping call, SN=%z	ACS Chassis run-time error in engine.	Contact support.	ACS
110584	ERROR	SLEE[%d]: slee_acs(%d) WARNING acsSLEEChassis_t::callEngine=%d acsChassis.cc@%d: %s %d, line %z Unexpected response type	ACS Chassis received an event for an unknown call.	Contact support.	ACS
110585	ERROR	SLEE[%d]: slee_acs(%d) WARNING acsSLEEChassis_t::callEngine=%d acsChassis.cc@%d: %s %d, line ZZZInvalid Attempt at Call Processing	ACS Chassis received an event for an unknown call.	Contact support.	ACS
110586	ERROR	SLEE[%d]: slee_acs(%d) WARNING acsSLEEChassis_t::callEngine=%d acsChassis.cc@%d: %s %d, line %z Unexpected message type	ACS Chassis received an event for an unknown call.	Contact support.	ACS
110587	ERROR	SLEE[%d]: slee_acs(%d) WARNING acsSLEEChassis_t::callEngine=%d acsChassis.cc@%d: %s %d, line %z Unexpected action type	ACS Chassis received an event for an unknown call.	Contact support.	ACS
110588	ERROR	SLEE[%d]: slee_acs(%d) WARNING acsSLEEChassis_t::callEngine=%d acsChassis.cc@%d: %s %d, line %z Bad Charging report, no free call set	ACS Chassis received an event for an unknown call.	Contact support.	ACS
110589	CRITICAL	SLEE[%d]: slee_acs(%d) ERROR storeProfileField=%d acsChassisProfile.pc@%d: Memory Allocation Error.	Insufficient memory to perform desired action due to internal software error.	Refer to UNIX/application expert first (Check the following). 1) Rogue processes consuming memory 2) Unusually large memory consumption for an individual binary. Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110590	CRITICAL	SLEE[%d]: slee_acs(%d) ERROR acsChassisReLoadProfiles=%d acsService.pc@%d:%z	Insufficient memory to perform desired action due to internal software error.	Refer to UNIX/application expert first (Check the following). 1) Rogue processes consuming memory 2) Unusually large memory consumption for an individual binary. Finally contact support.	ACS
110591	CRITICAL	SLEE[%d]: slee_acs(%d) ERROR acsChassisMain=%d acsChassis.cc@%d: Memory Allocation Error.	Insufficient memory to perform desired action due to internal software error.	Refer to UNIX/application expert first (Check the following). 1) Rogue processes consuming memory 2) Unusually large memory consumption for an individual binary. Finally contact support.	ACS
110592	CRITICAL	SLEE[%d]: slee_acs(%d) ERROR acsChassisServiceSetup=%d acsChassisService.c@%d: Memory Allocation Error.	Insufficient memory to perform desired action due to internal software error.	Refer to UNIX/application expert first (Check the following). 1) Rogue processes consuming memory 2) Unusually large memory consumption for an individual binary. Finally contact support.	ACS
110593	CRITICAL	SLEE[%d]: slee_acs(%d) ERROR acsSLEEChassis_t::handleInitCall =%d acsChassis.cc@%d: Memory Allocation Error.	Insufficient memory to perform desired action due to internal software error.	Refer to UNIX/application expert first (Check the following). 1) Rogue processes consuming memory 2) Unusually large memory consumption for an individual binary. Finally contact support.	ACS
110594	CRITICAL	SLEE[%d]: slee_acs(%d) ERROR dispError=%d cmnMfile.c@%d: error buffer overflow	Insufficient memory to perform desired action due to internal software error.	Refer to UNIX/application expert first (Check the following). 1) Rogue processes consuming memory 2) Unusually large memory consumption for an individual binary. Finally contact support.	ACS
110595	ERROR	SLEE[%d]: slee_acs(%d) ERROR Engine=%d acsEngineNodeProcessors.c@%d:%z	ACS Chassis failed to map ACS language for this announcement ID.	Contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110596	CRITICAL	SLEE[%d]: slee_acs(%d) CRITICAL: acsReplicationAction::classInit: Failed registration of acsReplicationAction chassis action	acsReplication chassis action failed to register with the ACS Chassis successfully.	Contact support.	ACS
110597	CRITICAL	SLEE[%d]: slee_acs(%d) CRITICAL: acsReplicationAction::classInit: Failed to open slee api	acsReplication chassis action failed to register with the ACS Chassis successfully.	Contact support.	ACS
110598	CRITICAL	SLEE[%d]: slee_acs(%d) CRITICAL: acsReplicationAction::doAction: could not locate Replication Interface - did you name it Replication in the SLEE configuration file?	acsReplication chassis action failed to find the SLEE Replication IF which should be named Replication in the SLEE.cfg file.	Refer to application expert. Verify that all the necessary parameters exist in the SLEE.cfg file found in /IN/service_packages/SLEE/etc. If unsure of configuration details then contact support.	ACS
110599	CRITICAL	SLEE[%d]: slee_acs(%d) CRITICAL: No matching ServiceEntry lines - check installation	The ACS.conf file is missing a ServiceEntry parameter.	Refer to application expert. Verify that all the necessary parameters exist in the ACS.conf file found in /IN/service_packages/ACS/etc. If unsure of configuration details then contact support.	ACS
110600	CRITICAL	SLEE[%d]: slee_acs(%d) CRITICAL: translateNumber called without setup	ACS Chassis failed to perform number translation mappings successfully.	Contact support.	ACS
110601	ERROR	SLEE[%d]: slee_acs(%d) ERROR acsSLEEChassis_t::acsSLEEChassis_t csStatsEventCounter.cc@d: Stats interface not found Call Dropped.	ACS Chassis failed to perform mid-call triggering successfully - failed to retrieve call context.	Contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110602	ERROR	SLEE[%d]: slee_acs(%d) ERROR acsSLEEChassis_t::FindSRFIPComponent=%d acsChassisTelephony.cc@%d:%z	ACS Chassis cannot find the current Specialised Resource Function.	Contact support.	ACS
110603	ERROR	SLEE[%d]: slee_acs(%d) ERROR acsSLEEChassis_t::processCall=%d acsChassis.cc@%d: Too many outstanding actions.	ACS Chassis failed to process this chassis action - too many outstanding actions.	Contact support.	ACS
110604	ERROR	SLEE[%d]: slee_acs(%d) ERROR maskSignals=%d cmnSignals.c@%d:%z	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110605	ERROR	SLEE[%d]: slee_acs(%d) ERROR unmaskSignals=%d cmnSignals.c@%d:%z	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110606	ERROR	SLEE[%d]: slee_acs(%d) ERROR: absMacro checkForCreditCardDetails:select from abs_credit_card_details : ORA-%d: converting column overflows integer datatype	ORACLE error: (ORA-01455): converting column overflows integer datatype - data returned from table may be invalid.	Refer ro ORACLE expert first. Ensure that credit card details do not exceed this data type. If problem persists contact support.	ACS
110607	ERROR	SLEE[%d]: slee_acs(%d) ERROR: ACS Plugin %s %d returned FALSE from sharedLibraryInit	Error when trying to register this feature node.	Contact support. No further information can be obtained.	ACS
110608	ERROR	SLEE[%d]: slee_acs(%d) ERROR: ACS_FN_TYPE has is_macro FALSE for fast_keyZZZ	is_macro field of ACS_FN_TYPE(public synonym) is set incorrectly - should be 1 for the feature node with this fast_key.	Refer to ORACLE expert first. Change the is_macro field of the ACS_FN_TYPE(public synonym) table to 1. Notify support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110609	ERROR	SLEE[%d]: slee_acs(%d) ERROR: acsChassisActionHandler::doAction() returned false; pluginZZZ	This chassis action failed to register with the ACS Chassis successfully.	Contact support.	ACS
110610	ERROR	SLEE[%d]: slee_acs(%d) ERROR: acsChassisActionSendMessage: Cannot get SleeApplicationAPI	ACS Chassis failed to send SMS - could not retrieve SleeApplicationAPI.	Contact support.	ACS
110611	ERROR	SLEE[%d]: slee_acs(%d) ERROR: acsChassisActionSSMHandler: unable to get notification IF	acsSendMessage chassis action failed to find the SLEE Notification IF which should be named Notification in the SLEE.cfg file.	Refer to application expert. Verify that all the necessary parameters exist in the SLEE.cfg file found in /IN/service_packages/SLEE/etc. If unsure of configuration details then contact support.	ACS
110612	ERROR	SLEE[%d]: slee_acs(%d) ERROR: acsChassisActionSSMHandler: unable to get SLEE application API	acsSendMessage chassis action failed to register with the ACS Chassis successfully.	Contact support.	ACS
110613	ERROR	SLEE[%d]: slee_acs(%d) ERROR: acsChassisMain: Failed to process INAP component	ACS Chassis failed to process the INAP component for this call.	Contact support.	ACS
110614	ERROR	SLEE[%d]: slee_acs(%d) ERROR: acsChassisMain: Null dialog on dialog closed, callID=%d	Encountered a NULL dialog on a dialog that is closed for this callID.	Contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110615	ERROR	SLEE[%d]: slee_acs(%d) ERROR: acsChassisPerformLoad: Svc Ldr returned error	acsServiceLoader encountered an error when trying to load this control plan - attempting to continue with existing loaded control plan.	If problem persists contact support.	ACS
110616	ERROR	SLEE[%d]: slee_acs(%d) ERROR: acsChassisReplicationUpdateProfi le: Cannot get Notification IF	ACS Chassis failed to send SMS - could not find the SLEE Notification IF which should be named Notification in the SLEE.cfg file.	Refer to application expert. Verify that all the necessary parameters exist in the SLEE.cfg file found in /IN/service_packages/SLEE/etc. If unsure of configuration details then contact support.	ACS
110617	ERROR	SLEE[%d]: slee_acs(%d) ERROR: acsChassisReplicationUpdateProfi le: Cannot get Replication IF	acsReplication chassis action failed to find the SLEE Replication IF which should be named Replication in the SLEE.cfg file.	Refer to application expert. Verify that all the necessary parameters exist in the SLEE.cfg file found in /IN/service_packages/SLEE/etc. If unsure of configuration details then contact support.	ACS
110618	ERROR	SLEE[%d]: slee_acs(%d) ERROR: acsChassisReplicationUpdateProfi le: Cannot get SleeApplicationAPI	acsReplication chassis action failed to register with the ACS Chassis successfully.	Contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110619	ERROR	SLEE[%d]: slee_acs(%d) ERROR: acsChassisSetup: Database connect failed	ACS Chassis failed setup - cannot connect to ORACLE.	Refer to ORACLE/application expert first (Check the following). 1) Verify that ORACLE is running through checking the status of the listener(lsnrctl) and restart ORACLE only if neccessary. 2) Check the environment variables and/or configuration files: ORACLE_SID(environment), tnsnames.ora(configuration file), listener.ora(configuration file). Verify that the username and password for the current machine is correct. 3) Observe startup output for errors. Finally contact support.	ACS
110620	ERROR	SLEE[%d]: slee_acs(%d) ERROR: acsChassisSetup: Plugin-load failed	ACS Chassis failed setup - cannot load this plugin.	Assuming basic UNIX skills (Check the following). 1) Check validity and permissions of this shared library in /IN/service_packages/ACS/lib. 2) Verify the entry exists for this shared library in the ACS.conf file found in /IN/service_packages/ACS/etc.	ACS
110621	ERROR	SLEE[%d]: slee_acs(%d) ERROR: acsChassisSetup: Setup cache failed	ACS Chassis failed setup - cannot create control plan cache.	No resolution.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110622	ERROR	SLEE[%d]: slee_acs(%d) ERROR: acsChassisSetup: Setup CDR subsystem failed	ACS Chassis failed setup - failed to establish CDR subsystem for CDR IF.	Refer to application expert. Verify that all the necessary parameters exist in the ACS.conf file found in /IN/service_packages/ACS/etc. If unsure of configuration details then contact support.	ACS
110623	ERROR	SLEE[%d]: slee_acs(%d) ERROR: acsChassisSetup: Setup digit translation failed	ACS Chassis failed setup - cannot create digit translation map.	No resolution.	ACS
110624	ERROR	SLEE[%d]: slee_acs(%d) ERROR: acsChassisSetup: Setup emergency numbers failed	ACS Chassis failed setup - failed to setup emergency numbers.	Refer to application expert. Verify that all the necessary parameters exist in the ACS.conf file found in /IN/service_packages/ACS/etc. If unsure of configuration details then contact support.	ACS
110625	ERROR	SLEE[%d]: slee_acs(%d) ERROR: acsChassisSetup: Setup engine parameters failed	ACS Chassis failed setup - failed to setup parameters for ACS Engine.	Refer to application expert. Verify that all the necessary parameters exist in the ACS.conf file found in /IN/service_packages/ACS/etc. If unsure of configuration details then contact support.	ACS
110626	ERROR	SLEE[%d]: slee_acs(%d) ERROR: acsChassisSetup: Setup ExtensionNumber parameters failed	ACS Chassis failed setup - failed to setup extension numbers.	Refer to application expert. Verify that all the necessary parameters exist in the ACS.conf file found in /IN/service_packages/ACS/etc. If unsure of configuration details then contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110627	ERROR	SLEE[%d]: slee_acs(%d) ERROR: acsChassisSetup: Setup language mapping failed	ACS Chassis failed setup - cannot create language mappings.	Contact support.	ACS
110628	ERROR	SLEE[%d]: slee_acs(%d) ERROR: acsChassisSetup: Setup service keys failed	ACS Chassis failed setup - failed to setup service keys.	Refer to application expert. Verify that all the necessary parameters exist in the ACS.conf file found in /IN/service_packages/ACS/etc. If unsure of configuration details then contact support.	ACS
110629	ERROR	SLEE[%d]: slee_acs(%d) ERROR: acsChassisSetup: Setup SRF parameters failed	ACS Chassis failed setup - failed to setup specialised resource functions.	Refer to application expert. Verify that all the necessary parameters exist in the ACS.conf file found in /IN/service_packages/ACS/etc. If unsure of configuration details then contact support.	ACS
110630	ERROR	SLEE[%d]: slee_acs(%d) ERROR: acsChassisSetup: Unable to configure NOA rules	ACS Chassis failed setup - cannot create number normalisation rules.	Contact support.	ACS
110631	ERROR	SLEE[%d]: slee_acs(%d) ERROR: acsChassisSetupExtensionNumbers() : Failed to open acs.conf	Attempting to read the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110632	ERROR	SLEE[%d]: slee_acs(%d) ERROR: acsChassisSetupSrfs() : Failed to open acs.conf	Attempting to read the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS
110633	ERROR	SLEE[%d]: slee_acs(%d) ERROR: acsNumberNormaliseAction Failed to registerZZZ	acsNumberNormalisation chassis action failed to register with the ACS Chassis successfully.	Contact support.	ACS
110634	ERROR	SLEE[%d]: slee_acs(%d) ERROR: acsReplicationAction::doAction: Failed to reserve a sleeLongReplicationEvent	acsReplication chassis action failed to register with the ACS Chassis successfully.	Contact support.	ACS
110635	ERROR	SLEE[%d]: slee_acs(%d) ERROR: acsReplicationAction::doAction: Failed to reserve a sleeReplicationEvent	acsReplication chassis action failed to register with the ACS Chassis successfully.	Contact support.	ACS
110636	ERROR	SLEE[%d]: slee_acs(%d) ERROR: Attempt to duplicate fast_key %s %d in acsEngineRegisterFNType	Error when trying to register this fast_key - must be unique.	Contact support. No further information can be obtained.	ACS
110637	ERROR	SLEE[%d]: slee_acs(%d) ERROR: Attempted to register more than MAX_CHASSIS_EVENT_HANDLERS on a single call!	Error when trying to register this chassis event handler - maximum already registered for this call.	Contact support. No further information can be obtained.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110638	ERROR	SLEE[%d]: slee_acs(%d) ERROR: Call ID %d TCAP_ABORT received with null context	TC_ABORT message received with a null ACS Chassis context.	Contact support.	ACS
110639	ERROR	SLEE[%d]: slee_acs(%d) ERROR: Call ID %d TC_ABORT from external IP but no outstanding operation.	TC_ABORT message received for an external IP that has no outstanding actions.	Contact support.	ACS
110640	ERROR	SLEE[%d]: slee_acs(%d) ERROR: Call ID %d TC_ABORT from external IP but processCall() failed.	TC_ABORT message received for an external IP but we failed to process the call successfully.	Contact support.	ACS
110641	ERROR	SLEE[%d]: slee_acs(%d) ERROR: Call ID %d TCAP_ABORT is not last event (%d)	TC_ABORT message received which is not the last event on this dialog.	Contact support.	ACS
110642	ERROR	SLEE[%d]: slee_acs(%d) ERROR: collectMultipleDigits: Min digits (%s %d) exceeds switch limit (%s %d)	The minimum prompt digits to collect value for this call exceeds the MaxPromptDigits value extracted from the ACS.conf configuration file.	Contact support. No further information can be obtained.	ACS
110643	ERROR	SLEE[%d]: slee_acs(%d) ERROR: compile pattern error %s %d on pattern %s %d, Node %d	Error when trying to compile this feature node.	Contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110644	ERROR	SLEE[%d]: slee_acs(%d) ERROR: Could not find symbol sharedLibraryInit in ACS PluginZZZ	This shared library is missing/corrupt.	Assuming basic UNIX skills (Check the following). 1)Check validity and permissions of the acsTZCompiler shared library in /IN/service_packages/ACS/lib. 2) Verify the entry exists for this shared library in the ACS.conf file found in /IN/service_packages/ACS/etc.	ACS
110645	ERROR	SLEE[%d]: slee_acs(%d) ERROR: Could not load ACS PluginZZZ	ACS Plugin shared library is missing/corrupt.	Assuming basic UNIX skills (Check the following). 1)Check validity and permissions of the ACS Plugin shared library in /IN/service_packages/ACS/lib. 2) Verify the entry exists for this shared library in the ACS.conf file found in /IN/service_packages/ACS/etc.	ACS
110646	ERROR	SLEE[%d]: slee_acs(%d) ERROR: %s 123doAction: Chassis plugin %d failure. Dropping call.	The ACS Chassis action failed to invoke this pluggable chassis action - call is being dropped.	Contact support.	ACS
110647	ERROR	SLEE[%d]: slee_acs(%d) ERROR: doAction: Unknown action code %d invoked. Dropping call.	The ACS Chassis received an unknown action code - call is being dropped.	Contact support.	ACS
110648	ERROR	SLEE[%d]: slee_acs(%d) ERROR: doChainCall: Cannot alloc profile	ACS Chassis failed to copy profile successfully.	Contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110649	ERROR	SLEE[%d]: slee_acs(%d) ERROR: doChainCall: Cannot initialise engine	ACS Chassis failed to initialise engine successfully - failed to retrieve call context.	Contact support.	ACS
110650	ERROR	SLEE[%d]: slee_acs(%d) ERROR: doChainCall: Have no processCall and no control plan	ACS Chassis failed to retrieve either a service entry(service loader) or a control plan.	Contact support.	ACS
110651	ERROR	SLEE[%d]: slee_acs(%d) ERROR: Failed to connect to oracle as user %s %d (password hidden)	Cannot connect to ORACLE.	Refer to ORACLE/application expert first (Check the following). 1) Verify that ORACLE is running through checking the status of the listener(lsnrctl) and restart ORACLE only if neccessary. 2) Check the environment variables and/or configuration files: ORACLE_SID(environment), tnsnames.ora(configuration file), listener.ora(configuration file). Verify that the username and password for the current machine is correct. 3) Observe startup output for errors. Finally contact support.	ACS
110652	ERROR	SLEE[%d]: slee_acs(%d) ERROR: handleINAPComponent: IDP, Existing Context	Received TC_INVOKE message with an IDP with an existing call context (this is the second IDP for this call).	Contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110653	ERROR	SLEE[%d]: slee_acs(%d) ERROR: handleINAPComponent: No context, No IDP	Received TC_INVOKE message without an IDP nor a call context.	Contact support.	ACS
110654	ERROR	SLEE[%d]: slee_acs(%d) ERROR: handleINAPComponent: Received TCAP_REJECT - operationErrorId is %d	Received TC_REJECT message.	Contact support.	ACS
110655	ERROR	SLEE[%d]: slee_acs(%d) ERROR: handleINAPComponent: Received unhandled componentType %d with operationErrorId %d	Received unknown TCAP component type.	Contact support.	ACS
110656	ERROR	SLEE[%d]: slee_acs(%d) ERROR: handleInitCall: No SVC LIB process, no Control Plan	ACS Chassis failed to retrieve either a service entry(service loader) or a control plan.	Contact support.	ACS
110657	ERROR	SLEE[%d]: slee_acs(%d) ERROR: Looping with no stack in processCall	Attempting to process a call with no outstanding actions.	Contact support.	ACS
110658	ERROR	SLEE[%d]: slee_acs(%d) ERROR: moveOldCdrs: stat failed - no such fileZZZ	Attempting to obtain the status of the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110659	ERROR	SLEE[%d]: slee_acs(%d) ERROR: moveOldCdrs: stat failed - search permission denied	Attempting to obtain the status of the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS
110660	ERROR	SLEE[%d]: slee_acs(%d) ERROR: moveOldCdrs: stat failed while processing file %s %d - reason:%z	Attempting to obtain the status of the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS
110661	ERROR	SLEE[%d]: slee_acs(%d) ERROR: Negative (chassis-internal) actionType received from Engine: %d	ACS Chassis received an invalid action code for this call.	Contact support.	ACS
110662	ERROR	SLEE[%d]: slee_acs(%d) ERROR: No CP data for CLI=%s %d DN=%s %d	No control plan found for this CLI.	Attempt to recompile the current control plan. If problem persists, contact support.	ACS
110663	ERROR	SLEE[%d]: slee_acs(%d) ERROR: No CP struct for CLI=%s %d DN=%s %d	No control plan found for this CLI.	Attempt to recompile the current control plan. If problem persists, contact support.	ACS
110664	ERROR	SLEE[%d]: slee_acs(%d) ERROR: No Service for NAME=%z	The ACS.conf file contains a ServiceEntry line where the service cannot be matched.	Refer to application expert. Verify that all the necessary parameters exist in the ACS.conf file found in /IN/service_packages/ACS/etc. If unsure of configuration details then contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110665	ERROR	SLEE[%d]: slee_acs(%d) ERROR: Open Failed %s %d (%d bytes lost)	Attempting to read the current file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS
110666	ERROR	SLEE[%d]: slee_acs(%d) ERROR: Pass 1 config file read errorZZZ	Attempting to read the ACS.conf configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110667	ERROR	SLEE[%d]: slee_acs(%d) ERROR: Pass 2 config file read errorZZZ	Attempting to read the ACS.conf configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS
110668	ERROR	SLEE[%d]: slee_acs(%d) ERROR: performProfileReplication: No matching table for template %s %d	ORACLE error trying to perform replication - unknown table.	Refer to ORACLE/application expert first (Check the following). 1) Verify that ORACLE is running through checking the status of the listener(lsnrctl) and restart ORACLE only if neccessary. 2) Check the environment variables and/or configuration files: ORACLE_SID(environment), tnsnames.ora(configuration file), listener.ora(configuration file). 3) Verify that the username and password for the current machine is correct. 4) Observe startup output for errors. Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110669	ERROR	SLEE[%d]: slee_acs(%d) ERROR: Problem reading ACS_FN_TYPE in acsEngine_ReadMacroNodeDescripti on	ORACLE error trying to access ACS_FN_TYPE(public synonym) table.	Refer to ORACLE/application expert first (Check the following). 1) Verify that ORACLE is running through checking the status of the listener(lsnrctl) and restart ORACLE only if neccessary. 2) Check the environment variables and/or configuration files: ORACLE_SID(environment), tnsnames.ora(configuration file), listener.ora(configuration file). 3) Verify that the username and password for the current machine is correct. 4) Observe startup output for errors. Finally contact support.	ACS
110670	ERROR	SLEE[%d]: slee_acs(%d) ERROR: Problem reading macro node description for fast_key %s %d from database in acsEngineRegisterFNType	ORACLE error trying to access ACS_FN_TYPE(public synonym) table.	Refer to ORACLE/application expert first (Check the following). 1) Verify that ORACLE is running through checking the status of the listener(lsnrctl) and restart ORACLE only if neccessary. 2) Check the environment variables and/or configuration files: ORACLE_SID(environment), tnsnames.ora(configuration file), listener.ora(configuration file). 3) Verify that the username and password for the current machine is correct. 4) Observe startup output for errors. Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110671	ERROR	SLEE[%d]: slee_acs(%d) ERROR: processCall - Svc Lib returned ERROR/unknown	ACS Chassis failed to retrieve either a service entry(service loader) or the service loader returned an error.	Contact support.	ACS
110672	ERROR	SLEE[%d]: slee_acs(%d) ERROR: semctl() error:%z	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110673	ERROR	SLEE[%d]: slee_acs(%d) ERROR: semget() error:%z	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110674	ERROR	SLEE[%d]: slee_acs(%d) ERROR: semop() error:%z	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110675	ERROR	SLEE[%d]: slee_acs(%d) ERROR: shmatt() error:%z	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110676	ERROR	SLEE[%d]: slee_acs(%d) ERROR: shmAttach: Cannot get semID from semKey %d	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110677	ERROR	SLEE[%d]: slee_acs(%d) ERROR: shmctl() error:%z	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110678	ERROR	SLEE[%d]: slee_acs(%d) ERROR: shmget() error:%z	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110679	ERROR	SLEE[%d]: slee_acs(%d) ERROR: smsTryRecordStats: Cannot attach to SHM	Kernel error on current machine.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110680	ERROR	SLEE[%d]: slee_acs(%d) ERROR: Unable to open configuration fileZZZ	Attempting to read the ACS.conf configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS
110681	ERROR	SLEE[%d]: slee_acs(%d) ERROR: Unknown pluggable-action-type %d	Received unknown pluggable chassis action type.	Contact support.	ACS
110682	ERROR	SLEE[%d]: slee_acs(%d) ERROR: Write Failed %s %d (%d bytes lost)	Attempting to write to the current file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS
110683	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE: cant catch SIGHUP	Kernel communication/disk error.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110684	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE: cant catch SIGTERM	Kernel communication/disk error.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110685	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE: cant catch SIGUSR1	Kernel communication/disk error.	Refer to UNIX/application expert first. If problem persists then contact support.	ACS
110686	WARNING	SLEE[%d]: slee_acs(%d) WARNING acsSLEEChassis_t::collectMultipleDigits=%d acsChassisTelephony.cc@d: Invalid variable part type.	ACS Chassis received a collect single digit request with an invalid variable type.	Contact support.	ACS
110687	WARNING	SLEE[%d]: slee_acs(%d) WARNING acsSLEEChassis_t::collectSingleDigit=%d acsChassisTelephony.cc@d: Invalid variable part type.	ACS Chassis received a collect multiple digit request with an invalid variable type.	Contact support.	ACS
110688	WARNING	SLEE[%d]: slee_acs(%d) WARNING acsSLEEChassis_t::getCallInfo IDP_MISSING_PARAMETER CalledPartyNumber	ACS Chassis received IDP with missing information - no called party number specified.	Contact support.	ACS
110689	WARNING	SLEE[%d]: slee_acs(%d) WARNING acsSLEEChassis_t::handleINAPComponent=%d acsChassisTelephony.cc@d: Non-management or InitialDP without call context, IGNORED	TC_RESULT message invalid - received a non-management or an IDP with a null context.	Contact support.	ACS
110690	WARNING	SLEE[%d]: slee_acs(%d) WARNING acsSLEEChassis_t::handleInitCall=%d acsChassis.cc@d: Bad initialDP message.	Unable to determine the call info from the call context for this IDP.	Contact support.	ACS
110691	WARNING	SLEE[%d]: slee_acs(%d) WARNING acsSLEEChassis_t::handleInitCall=%d acsChassis.cc@d: Unable to find Call Type.	Unable to determine the call type from the call context for this IDP.	Contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110692	WARNING	SLEE[%d]: slee_acs(%d) WARNING acsSLEEChassis_t::playAnnouncement=%d acsChassisTelephony.cc@%d: Invalid variable part type.	ACS Chassis received a play announcement request with an invalid variable type.	Contact support.	ACS
110693	WARNING	SLEE[%d]: slee_acs(%d) WARNING: acsChassisActionHandler::doAction() set waitingForExternal, but we cant transmit that information back to the chassis!	ACS Chassis Action waiting, but not able to receive a reply from the acs chassis.	Contact support.	ACS
110694	WARNING	SLEE[%d]: slee_acs(%d) WARNING: acsChassisLoadService: ACS - No CP for SN %s %d	Cannot find this control plan in the ACS_CALL_PLAN(public synonym) table for this called party number.	Refer to application expert. Verify that this control plan exists - name field of ACS_CALL_PLAN(public synonym) table for this calling party number. If unsure of control plan details then contact support	ACS
110695	WARNING	SLEE[%d]: slee_acs(%d) WARNING: acsChassisLoadService: ACS Named - No CP named %s %d	Cannot find this control plan in the ACS_CALL_PLAN(public synonym) table for this called party number.	Refer to application expert. Verify that this control plan exists - name field of ACS_CALL_PLAN(public synonym) table for this calling party number. If unsure of control plan details then contact support	ACS
110696	WARNING	SLEE[%d]: slee_acs(%d) WARNING: acsChassisLoadService: ACS_Outgoing - No CP for CN %s %d	Cannot find this control plan in the ACS_CALL_PLAN(public synonym) table for this calling party number.	Refer to application expert. Verify that this control plan exists - name field of ACS_CALL_PLAN(public synonym) table for this called party number. If unsure of control plan details then contact support	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110697	WARNING	SLEE[%d]: slee_acs(%d) WARNING: acsChassisMain: Call ID %d Initiating event type %s %d (%d) did not generate context	ACS Chassis received an incoming call which is a non-TCAP event with an invalid call context.	Contact support.	ACS
110698	WARNING	SLEE[%d]: slee_acs(%d) WARNING: acsChassisMain: No Event	ACS Chassis received an incoming call which is an unknown event type.	Contact support.	ACS
110699	WARNING	SLEE[%d]: slee_acs(%d) WARNING: acsChassisMain: TCAP components to send, no dialog	ACS Chassis has TCAP event to send but no dialog for this call.	Contact support.	ACS
110700	WARNING	SLEE[%d]: slee_acs(%d) WARNING: acsChassisMain: TCAP IP End set, but no components to send	ACS Chassis has TCAP IP End event to send but no components to send.	Contact support.	ACS
110701	WARNING	SLEE[%d]: slee_acs(%d) WARNING: acsChassisMain: Unknown management event typeZZZ	ACS Chassis received an incoming call which is an unknown management event type.	Contact support.	ACS
110702	WARNING	SLEE[%d]: slee_acs(%d) WARNING: acsChassisMain: Unknown non-management event type %s %d received	ACS Chassis received an incoming call which is an unknown non-management event type.	Contact support.	ACS
110703	WARNING	SLEE[%d]: slee_acs(%d) WARNING: acsChassisNotifyPluginsCallEnded : no plugin context available	ACS Chassis can not retrieve the pluggable chassis action context - context is not valid.	Contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110704	WARNING	SLEE[%d]: slee_acs(%d) WARNING: acsChassisSetupCDR: CdrAma invalid (%d). Disabling CDR to AMA	The ACS.conf file contains an invalid CdrAma parameter.	Refer to application expert. Verify that all the necessary parameters exist in the ACS.conf file found in /IN/service_packages/ACS/etc. If unsure of configuration details then contact support.	ACS
110705	WARNING	SLEE[%d]: slee_acs(%d) WARNING: acsChassisSetupCDR: CdrAma not found. Disabling CDR to AMA	The ACS.conf file contains an invalid CdrAma parameter.	Refer to application expert. Verify that all the necessary parameters exist in the ACS.conf file found in /IN/service_packages/ACS/etc. If unsure of configuration details then contact support.	ACS
110706	WARNING	SLEE[%d]: slee_acs(%d) WARNING: acsChassisSetupCDR: CdrFci invalid (%d). Disabling CDR to FCI	The ACS.conf file contains an invalid CdrFci parameter.	Refer to application expert. Verify that all the necessary parameters exist in the ACS.conf file found in /IN/service_packages/ACS/etc. If unsure of configuration details then contact support.	ACS
110707	WARNING	SLEE[%d]: slee_acs(%d) WARNING: acsChassisSetupCDR: CdrFci not found. Disabling CDR to FCI	The ACS.conf file contains an invalid CdrFci parameter.	Refer to application expert. Verify that all the necessary parameters exist in the ACS.conf file found in /IN/service_packages/ACS/etc. If unsure of configuration details then contact support.	ACS
110708	WARNING	SLEE[%d]: slee_acs(%d) WARNING: acsChassisSetupCDR: CdrFile invalid (%d). Disabling CDR to file	The ACS.conf file contains an invalid CdrFile parameter.	Refer to application expert. Verify that all the necessary parameters exist in the ACS.conf file found in /IN/service_packages/ACS/etc. If unsure of configuration details then contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110709	WARNING	SLEE[%d]: slee_acs(%d) WARNING: acsChassisSetupCDR: CdrFile not found. Disabling CDR to file	The ACS.conf file contains an invalid CdrFile parameter.	Refer to application expert. Verify that all the necessary parameters exist in the ACS.conf file found in /IN/service_packages/ACS/etc. If unsure of configuration details then contact support.	ACS
110710	WARNING	SLEE[%d]: slee_acs(%d) WARNING: acsSLEEChassis_t::findCallType: No service for %s %d	ACS Chassis can not retrieve the call type for this service handle.	Contact support.	ACS
110711	WARNING	SLEE[%d]: slee_acs(%d) WARNING: doAction: Event Logging is no longer available	ACS Chassis no longer supports event logging.	Contact support.	ACS
110712	WARNING	SLEE[%d]: slee_acs(%d) WARNING: handleINAPComponent: TCAP_U_ERROR: Unhandled error component %d	ACS Chassis has TCAP_U_ERROR event with an unknown error component.	Contact support.	ACS
110713	WARNING	SLEE[%d]: slee_acs(%d) WARNING: handleINAPComponent: TCAP_U_ERROR %d return for invoke %d on call %d, sent operation ID %d	Information only.	No resolution.	ACS
110714	WARNING	SLEE[%d]: slee_acs(%d) WARNING: Lookup of Chassis Action Type %s %d failed!	Received unknown pluggable chassis action type.	Contact support.	ACS
110715	WARNING	SLEE[%d]: slee_acs(%d) WARNING: Malformed Rule Ignored, %s %d: minDigits > maxDigits	Invalid number normalisation rule found in the ACS.conf configuration file - min digit value exceeds max digit value.	Refer to application expert. Verify that all the necessary parameters exist in the ACS.conf file found in /IN/service_packages/ACS/etc. If unsure of configuration details then contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110717	WARNING	SLEE[%d]: slee_acs(%d) WARNING: Rule %s %d: maxDigits constrained to %d from %d	Invalid number normalisation rule found in the ACS.conf configuration file - max digit value exceeded maximum permitted value and has been set to maximum permitted value.	Refer to application expert. Verify that all the necessary parameters exist in the ACS.conf file found in /IN/service_packages/ACS/etc. If unsure of configuration details then contact support.	ACS
110718	WARNING	SLEE[%d]: slee_acs(%d) WARNING: storeProfileField: No store function registered.	Unable to store profile field.	Contact support.	ACS
110719	ERROR	SLEE[%d]: slee_acs(%d) CRITICAL: Aiee! cmnPluginReleaseHandle received NULL handle!	Internal software error.	Contact support. No further information can be obtained.	ACS
110720	CRITICAL	SLEE[%d]: slee_acs(%d) CRITICAL: cmnPlugin: error loading library %s %d:%z	acsStatsMaster shared library is missing/corrupt.	Assuming basic UNIX skills (Check the following). 1)Check validity and permissions of the acsStatsMaster shared library in /IN/service_packages/MOB_PP/lib	ACS
110721	ERROR	SLEE[%d]: slee_acs(%d) ERROR: cmnDate::getLocalDate:%z	Internal software error.	No resolution. If problem persists then contact support.	ACS
110722	ERROR	SLEE[%d]: slee_acs(%d) ERROR: cmnProfileFindIndex: Profile corrupt (data pos misaligned)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110723	ERROR	SLEE[%d]: slee_acs(%d) ERROR: cmnProfileFindIndex: Profile corrupt (length < 0)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110724	ERROR	SLEE[%d]: slee_acs(%d) ERROR: cmnProfileFindIndex: Profile corrupt (offset + length > profileLength)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110725	ERROR	SLEE[%d]: slee_acs(%d) ERROR: cmnProfileFindIndex: Profile corrupt (offset < 0)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110726	ERROR	SLEE[%d]: slee_acs(%d) ERROR: cmnProfileFindIndex: Profile corrupt (offset > profileLength)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110727	ERROR	SLEE[%d]: slee_acs(%d) ERROR: cmnProfileFindIndex: Profile corrupt (TOC end > profileLength)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110728	ERROR	SLEE[%d]: slee_acs(%d) ERROR: cmnProfileFindTag: Profile corrupt (data pos misaligned)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110729	ERROR	SLEE[%d]: slee_acs(%d) ERROR: cmnProfileFindTag: Profile corrupt (length < 0)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110730	ERROR	SLEE[%d]: slee_acs(%d) ERROR: cmnProfileFindTag: Profile corrupt (offset + length > profileLength)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110731	ERROR	SLEE[%d]: slee_acs(%d) ERROR: cmnProfileFindTag: Profile corrupt (offset < 0)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110732	ERROR	SLEE[%d]: slee_acs(%d) ERROR: cmnProfileFindTag: Profile corrupt (offset > profileLength)	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110733	ERROR	SLEE[%d]: slee_acs(%d) ERROR: Remove tag: Corrupted, tag field data passes end of profile	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110734	ERROR	SLEE[%d]: slee_acs(%d) ERROR: Remove tag: Corrupted, tag length begins before profile	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110735	ERROR	SLEE[%d]: slee_acs(%d) ERROR: Remove tag: Corrupted, tag length field passes end of profile	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110736	ERROR	SLEE[%d]: slee_acs(%d) ERROR: Update block corrupt. Item offset is negative. Creating empty block.	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110737	ERROR	SLEE[%d]: slee_acs(%d) ERROR: Update block has no tags but is wrong size. Creating empty profile.	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110738	ERROR	SLEE[%d]: slee_acs(%d) ERROR: Update profile corrupt. Field goes past profile block len.	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110739	ERROR	SLEE[%d]: slee_acs(%d) ERROR: Update profile corrupt. Length goes past profile block len.	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110740	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE: gethostbyname:%z	Communications over the socket appears to have problems.	Refer to UNIX/application/LAN expert first (Check the following). 1) TCP/IP connection integrity. 2) Type netstat -na (see man netstat for more information) to determine the status of the listening socket for this connection. (Should be a configuration parameter). Finally contact support.	ACS
110741	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE: Select:%z	Communications over the socket appears to have problems.	Refer to UNIX/application/LAN expert first (Check the following). 1) TCP/IP connection integrity. 2) Type netstat -na (see man netstat for more information) to determine the status of the listening socket for this connection. (Should be a configuration parameter). Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110742	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE: socket:%z	Communications over the socket appears to have problems.	Refer to UNIX/application/LAN expert first (Check the following). 1) TCP/IP connection integrity. 2) Type netstat -na (see man netstat for more information) to determine the status of the listening socket for this connection. (Should be a configuration parameter). Finally contact support.	ACS
110743	WARNING	SLEE[%d]: slee_acs(%d) WARNING: cmnPluginLookupFunction: could not find symbol %s %d::%s %d:%z	acsStatsMaster shared library is missing/corrupt.	Assuming basic UNIX skills (Check the following). 1) Check validity and permissions of the acsStatsMaster shared library in /IN/service_packages/ACS/lib. 2) Verify the entry exists for this shared library in the ACS.conf file found in /IN/service_packages/ACS/etc.	ACS
110744	WARNING	SLEE[%d]: slee_acs(%d) WARNING: cmnPluginReleaseHandle: released already-released pluginZZZ	acsStatsMaster shared library is missing/corrupt.	Assuming basic UNIX skills (Check the following). 1) Check validity and permissions of the acsStatsMaster shared library in /IN/service_packages/ACS/lib. 2) Verify the entry exists for this shared library in the ACS.conf file found in /IN/service_packages/ACS/etc.	ACS
110745	WARNING	SLEE[%d]: slee_acs(%d) WARNING: Macro %s %d not found.	This macro node has been encountered in a control plan but the implementation details for this macro node cannot be found.	Contact support. No further information can be obtained.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110746	ERROR	SLEE[%d]: slee_acs(%d) ERROR: Could not stat() language index fileZZZ	Attempting to obtain the status of the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS
110747	ERROR	SLEE[%d]: slee_acs(%d) ERROR: Could not load either the requested language file or Default.lang! Falling back to untranslated strings.	Attempting to open the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS
110748	ERROR	SLEE[%d]: slee_acs(%d) ERROR: Could not read language index fileZZZ	Attempting to read the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS
110749	WARNING	SLEE[%d]: slee_acs(%d) WARNING: cmnConfigGetStringVector: unable to openZZZ	Attempting to open the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110750	WARNING	SLEE[%d]: slee_acs(%d) WARNING: Could not load language file %s %d! Falling back to Default.lang.	Attempting to read the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS
110751	WARNING	SLEE[%d]: slee_acs(%d) WARNING: Could not reload language file %s %d! Staying with in-core copy.	Attempting to read the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS
110752	WARNING	SLEE[%d]: slee_acs(%d) WARNING: getValue: unable to openZZZ	Attempting to read the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110753	WARNING	SLEE[%d]: slee_acs(%d) WARNING: Language translation dictionary in %s %d contained an invalid mapping line (no unescaped = sign) on or about line %d	Attempting to read the acsStatsMaster configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS
110754	WARNING	SLEE[%d]: slee_acs(%d) WARNING: cmnConfigGetChar: %z	Attempting to read the acsStatsMaster configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110755	WARNING	SLEE[%d]: slee_acs(%d) WARNING: cmnConfigGetFlag: %z	Attempting to read the acsStatsMaster configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS
110756	WARNING	SLEE[%d]: slee_acs(%d) WARNING: cmnConfigGetInteger: %z	Attempting to read the acsStatsMaster configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110757	WARNING	SLEE[%d]: slee_acs(%d) WARNING: cmnConfigGetString: %z	Attempting to read the acsStatsMaster configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS
110758	WARNING	SLEE[%d]: slee_acs(%d) WARNING: cmnConfigGetChar: %s %d not foundZZZ	Attempting to read the acsStatsMaster configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110759	WARNING	SLEE[%d]: slee_acs(%d) WARNING: cmnConfigGetFlag: %s %d not foundZZZ	Attempting to read the acsStatsMaster configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS
110760	WARNING	SLEE[%d]: slee_acs(%d) WARNING: cmnConfigGetInteger: %s %d not foundZZZ	Attempting to read the acsStatsMaster configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110761	WARNING	SLEE[%d]: slee_acs(%d) WARNING: cmnConfigGetString: %s %d not foundZZZ	Attempting to read the acsStatsMaster configuration file has resulted in an error.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS
110762	WARNING	SLEE[%d]: slee_acs(%d) WARNING: getConfig: No trailing : on sectionZZZ	Invalid line found in the currently selected language translation file.	Modify this line in the currently selected language translation file found in /IN/html/SMS/language.	ACS
110763	WARNING	SLEE[%d]: slee_acs(%d) WARNING: Language string not found in currently selected language database: %s %d	Invalid line found in the currently selected language translation file.	Modify this line in the currently selected language translation file found in /IN/html/SMS/language.	ACS
110764	CRITICAL	SLEE[%d]: slee_acs(%d) CRITICAL: malloc() returned NULL in build_filename (cmnLang.cc)! Out of memory!	Insufficient memory to perform desired action due to internal software error.	Refer to UNIX/application expert first (Check the following). 1) Rogue processes consuming memory 2) Unusually large memory consumption for an individual binary. Finally contact support.	ACS
110765	CRITICAL	SLEE[%d]: slee_acs(%d) CRITICAL: Out of memory in cmnLang.cc:processLine!	Insufficient memory to perform desired action due to internal software error.	Refer to UNIX/application expert first (Check the following). 1) Rogue processes consuming memory 2) Unusually large memory consumption for an individual binary. Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110766	CRITICAL	SLEE[%d]: slee_acs(%d) NOTICE allocate=%d cmnRangeOciFetch.c@%d: out of memory	Insufficient memory to perform desired action due to internal software error.	Refer to UNIX/application expert first (Check the following). 1) Rogue processes consuming memory 2) Unusually large memory consumption for an individual binary. Finally contact support.	ACS
110767	CRITICAL	SLEE[%d]: slee_acs(%d) WARNING strdup=%d loggedError.c@%d: out of memory	Insufficient memory to perform desired action due to internal software error.	Refer to UNIX/application expert first (Check the following). 1) Rogue processes consuming memory 2) Unusually large memory consumption for an individual binary. Finally contact support.	ACS
110768	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE: acs.conf contains old ServiceEntry fmt - field2 ignored	The ACS.conf file contains an old ServiceEntry line format - this service entry being ignored.	To prevent this NOTICE alarm, remove the entry from the ACS.conf file. If unsure of configuration details then contact support.	ACS
110769	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE: acsChassisSetup: CarrierCodeDisposal interpretationZZZ	Informational alarm indicating the value of the CarrierCodeDisposal parameter extracted from the ACS.conf configuration file.	No resolution.	ACS
110770	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE: acsChassisSetup: Setup successful	Informational alarm - ACS Chassis setup successfully completed.	No resolution.	ACS
110771	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE: acsChassisShutdown: Flush CDR buffers	Informational alarm - ACS Chassis shutting down - stopping the chassis CDR IF and flushing any remaining CDRs.	No resolution.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110772	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE: acsChassisTranslateSetup: Cannot load * hex mapping, setting default	Informational alarm - ACS Chassis creating digit translation has encountered an error loading # mapping, using default.	No resolution.	ACS
110773	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE: Configuring %d service entries	Informational alarm - ACS Chassis configuring this number of service entries.	No resolution.	ACS
110774	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE: Ignoring incompatible ServiceEntry line	The ACS.conf file contains an incompatible ServiceEntry line - this service entry being ignored.	To prevent this NOTICE alarm, remove the entry from the ACS.conf file. If unsure of configuration details then contact support.	ACS
110775	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE: Routing service %s %d to libraryZZZ	Informational alarm - ACS Chassis loading this shared library for this service entry.	No resolution.	ACS
110776	ERROR	SLEE[%d]: slee_acs(%d) ERROR main=%d slee_acs.cc@%d: Chassis configuration error, exiting	The ACS.conf file is missing a chassis parameter needed for configuring the ACS Chassis.	Refer to application expert. Verify that all the necessary parameters exist in the ACS.conf file found in /IN/service_packages/ACS/etc. If unsure of configuration details then contact support.	ACS
110777	ERROR	SLEE[%d]: slee_acs(%d) ERROR main=%d slee_acs.cc@%d: Chassis sanity check failed, exiting	ACS Chassis failed to restart successfully.	Contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110778	ERROR	SLEE[%d]: slee_acs(%d) ERROR main=%d slee_acs.cc@%d: Chassis performing normal shutdown, exiting	ACS Chassis shutdown successfully.	No resolution.	ACS
110779	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE: Startup SuccessfulZZZ	Informational alarm - slee_acs successfully started.	No resolution.	ACS
110780	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE oparse=%d cmnRangeOciFetch.c@%d:%z	Cannot connect to ORACLE.	Refer to ORACLE/application expert first (Check the following). 1) Verify that ORACLE is running through checking the status of the listener(lsnrctl) and restart ORACLE only if neccessary. 2) Check the environment variables and/or configuration files: ORACLE_SID(environment), tnsnames.ora(configuration file), listener.ora(configuration file). Verify that the username and password for the current machine is correct. 3) Observe startup output for errors. Finally contact support.	ACS
110781	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE: *** NULL pointer to CslInitialDP*	Informational alarm - ACS Chassis received an empty IDP and cannot extract the extension digits - this alarm will be raised in conjunction with another.	No resolution.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110782	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE: acsChassisSetup: IPProtocolInfo interpretationZZZ	Informational alarm - ACS Chassis extracted this value for the IPProtocolInfo parameter from the ACS.conf configuration file.	No resolution.	ACS
110783	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE: acsChassisSetup: Setup chassis global parameters	Informational alarm - ACS Chassis extracted some global parameters from the ACS.conf configuration file.	No resolution.	ACS
110784	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE: acsChassisShutdown: Shutdown called	Informational alarm - slee_acs successfully shutdown.	No resolution.	ACS
110785	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE: Cannot open %s %d for writing	Attempting to write to the current file has resulted in an error.	Assuming basic UNIX skills (Check the following). 1) Does the specified file exist? 2) Are the correct permissions set for the file? 3) Is the file corrupt, can it be opened? 4) Is the disk full? Finally contact support.	ACS
110786	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE: cmnConfigGetChar: %z	Successfully read this parameter in the acsStatsLocalSLEE configuration file.	No resolution.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110787	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE: cmnConfigGetFlag: %z	Successfully read this parameter in the acsStatsLocalSLEE configuration file.	No resolution.	ACS
110788	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE: cmnConfigGetInteger: %z	Successfully read this parameter in the acsStatsLocalSLEE configuration file.	No resolution.	ACS
110789	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE: cmnConfigGetString: %z	Successfully read this parameter in the acsStatsLocalSLEE configuration file.	No resolution.	ACS
110790	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE: acsChassisSetup: Connect to database	Informational alarm - slee_acs successfully connected to ORACLE.	No resolution.	ACS
110791	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE: acsChassisSetup: Setup called	Informational alarm - slee_acs beginning setup stage.	No resolution.	ACS
110792	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE: Environment variable SLEE_ACS_DEBUG set toZZZ	Informational alarm - slee_acs DEBUG set to this value.	No resolution.	ACS
110793	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE: restart: Unable to handle signal	Informational alarm - slee_acs restarting.	No resolution.	ACS
110794	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE: Attempt to respond to context.actions[index] with ACS_NO_ACTION_INITIATED initiator!	The pluggable chassis action is trying to respond to an invalid ACS Chassis event.	Contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110795	ERROR	SLEE[%d]: slee_acs(%d) CRITICAL: No %s %d entries in absScp.conf	Attempting to read the absScp.conf configuration file has resulted in an error - no parameters found.	Refer to UNIX/application expert first (Check the following). 1) Does the configuration file exist? 2) Are the correct permissions set for the configuration file? 3) Is the configuration file corrupt? 4) Have all the required parameters been entered in the configuration file? 5) Have all the configuration parameters been formatted correctly? Finally contact support.	ACS
110796	ERROR	SLEE[%d]: slee_acs(%d) ERROR: %s %d: Time remaining is outside acceptable range. reservationLength(%d), timeRemaining(%d).	An ABS feature node is attempting to reserve more time than what is available for this account.	Contact support.	ACS
110797	ERROR	SLEE[%d]: slee_acs(%d) ERROR: ABS getProfiles: Error getting account data	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110798	ERROR	SLEE[%d]: slee_acs(%d) ERROR: ABS LoadService: Error getting account data	Error reading the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110799	ERROR	SLEE[%d]: slee_acs(%d) ERROR: absBeActionHandler::doAction: Unsupported message type %d	This pluggable chassis action received an unknown	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110800	ERROR	SLEE[%d]: slee_acs(%d) ERROR: absSharedLibraryInit Failed to registerZZZ	Failed to register this shared library.	Assuming basic UNIX skills (Check the following). 1) Check validity and permissions of the acsStatsLocalSLEE shared library in /IN/service_packages/ACS/lib. 2) Verify the entry exists for this shared library in the ACS.conf file found in /IN/service_packages/ACS/etc.	ACS
110801	ERROR	SLEE[%d]: slee_acs(%d) ERROR: acsChassisStoreProfile: Failed to commit profile - code %d	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110802	ERROR	SLEE[%d]: slee_acs(%d) ERROR: acsChassisStoreProfile: Failed to update profile - code %d recs %d	Error updating the current users profile block.	Refer to ORACLE expert first. Verify the profile block exists and is not corrupted or invalid for this user, by referring to the profile field of the ABS_ACCT_REFERENCE(public synonym) table.	ACS
110803	ERROR	SLEE[%d]: slee_acs(%d) ERROR: action type %d	The ABS Account State Branch feature node received an unknown action and response type.	Contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110804	ERROR	SLEE[%d]: slee_acs(%d) ERROR: action type %d, resp type %d	The ABS Account State Branch feature node received an unknown action and response type.	Contact support.	ACS
110805	ERROR	SLEE[%d]: slee_acs(%d) ERROR: Cannot Get a Dialog - System Is Overloaded for call id %d.	The ABS ATB feature node is unable to get a dialog for this call - system is overloaded.	Contact support.	ACS
110806	ERROR	SLEE[%d]: slee_acs(%d) ERROR: Cannot Get a Dialog - Unable To Create Dialog For Call Id %d.	The ABS ATB feature node is unable to get a dialog for this call - system is overloaded.	Contact support.	ACS
110807	ERROR	SLEE[%d]: slee_acs(%d) ERROR: Cannot Get a Dialog - Unable To Get BE Client Handle For Call Id %d.	The ABS ATB feature node is unable to get a dialog for this call - system is overloaded.	Contact support.	ACS
110808	ERROR	SLEE[%d]: slee_acs(%d) ERROR: Cannot Get a Dialog - Unknown Reason When Getting Dialog for call id %d.	The ABS ATB feature node is unable to get a dialog for this call - system is overloaded.	Contact support.	ACS
110809	ERROR	SLEE[%d]: slee_acs(%d) ERROR: handleBEMessage: Unsupported message type %d	The pluggable chassis action received an unknown BE message type.	Contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110810	ERROR	SLEE[%d]: slee_acs(%d) ERROR: SMSCallInfo node: Attempted to play Short Message in an unconfigured language (%d); Defaulting to UNKNOWN language.	The ABS SMS call info feature node is unable to retrieve the configured language - defaulting to unknown language.	Contact support.	ACS
110811	ERROR	SLEE[%d]: slee_acs(%d) ERROR: Unknown recharge failure reason %d	The pluggable chassis action is unable to recharge voucher - unknown failure reason.	Contact support.	ACS
110812	ERROR	SLEE[%d]: slee_acs(%d) ERROR: Unknown redeem failure reason %d	The pluggable chassis action is unable to recharge voucher - unknown failure reason.	Contact support.	ACS
110813	WARNING	SLEE[%d]: slee_acs(%d) WARNING: SecondCurrency had zero base; Failure (acct_ref %z)	This users second currency base is not set.	Set the currency base for this user using the SMS screens. If unsure, the contact support.	ACS
110814	WARNING	SLEE[%d]: slee_acs(%d) WARNING: Too few or too many menu segments in absDoCCRecharge	There are too many credit card recharge rules for this product type.	Reduce the number of credit card rules for this product type using the SMS screens. If unsure, the contact support.	ACS
110815	WARNING	SLEE[%d]: slee_acs(%d) WARNING: UserCurrency had zero base; Failure (acct_ref %z)	This users currency base is not set.	Set the currency base for this user using the SMS screens. If unsure, the contact support.	ACS
110816	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE: Environment variable %s %d unset	Informational alarm - this environment variable unset.	No resolution.	ACS
110817	ERROR	SLEE[%d]: slee_acs(%d) ERROR: handleINAPComponent: TCAP_U_ERROR %d returned for unknown sent invoke %d	Received unknown TCAP component type.	Contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110818	ERROR	SLEE[%d]: slee_acs(%d) ERROR: handleINAPComponent: TCAP_U_ERROR %d return	Received unknown TCAP component type.	Contact support.	ACS
110819	ERROR	SLEE[%d]: slee_acs(%d) ERROR: No available applications	The watchdog would like to restart an application, however MAXAPPLICATIONINSTAN CES has been reached.	Refer to application expert. Modify SLEE config and restart SLEE.	ACS
110820	WARNING	SLEE[%d]: slee_acs(%d) ERROR: Received sig alarm - aborting SLEE processes.	Information only.	No resolution	ACS
110821	INFO	SLEE[%d]: slee_acs(%d) INFO: Started Application %s %d: PID: %d	Information only.	No resolution	ACS
110822	ERROR	SLEE[%d]: slee_acs(%d) ERROR: SIGABRT failed for process %d (%z).	An application/interfac e has died/finsihed, the watchdog will restart it	No resolution. If problem persists then contact support.	ACS
110823	ERROR	SLEE[%d]: slee_acs(%d) ERROR: SIGKILL failed for process %d (%z).	An application/interfac e has died/finsihed, the watchdog will restart it	No resolution. If problem persists then contact support.	ACS
110824	WARNING	SLEE[%d]: slee_acs(%d) WARNING: SIGABRT process %d.	An application/interfac e has stopped responding, the watchdog will restart it	No action needed, if repeated contact support	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110825	WARNING	SLEE[%d]: slee_acs(%d) WARNING: SIGKILL process %d.	An application/interface has stopped responding, the watchdog will restart it	No action needed, if repeated contact support	ACS
110826	ERROR	SLEE[%d]: slee_acs(%d) ERROR: Restarting application process %d.	The specified application is restarting.	No resolution.	ACS
110827	ERROR	SLEE[%d]: slee_acs(%d) ERROR: Restarting interface process %d.	The specified interface is restarting.	No resolution.	ACS
110828	ERROR	SLEE[%d]: slee_acs(%d) ERROR: Sending SIGABRT to application %s %d: PID: %d	Watchdog has sent an abort signal to the specified application.	No resolution.	ACS
110829	ERROR	SLEE[%d]: slee_acs(%d) ERROR: Sending SIGABRT to interface %s %d: PID: %d	Watchdog has sent an abort signal to the specified interface.	No resolution.	ACS
110830	ERROR	SLEE[%d]: slee_acs(%d) ERROR: Watchdog sending SIGABRT to application %s %d: PID: %d	Watchdog has sent an abort signal to the specified application.	No resolution.	ACS
110831	ERROR	SLEE[%d]: slee_acs(%d) ERROR: Watchdog sending SIGABRT to interface %s %d: PID: %d	Watchdog has sent an abort signal to the specified interface.	No resolution.	ACS
110832	ERROR	SLEE[%d]: slee_acs(%d) ERROR: Watchdog sending SIGABRT to PID: %d	Watchdog has sent an abort signal to the specified interface.	No resolution.	ACS
110833	INFO	SLEE[%d]: slee_acs(%d) INFO: Starting Interface %s %d: PID: %d	The specified interface is being started.	No resolution.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110834	INFO	SLEE[%d]: slee_acs(%d) SLEE Shutdown	The SLEE has stopped.	No resolution.	ACS
110835	INFO	SLEE[%d]: slee_acs(%d) SLEE Startup	The SLEE is starting up.	No resolution.	ACS
110836	CRITICAL	SLEE[%d]: slee_acs(%d) CRITICAL: Cannot connect to SLEE shared memory.	The watchdog process can not attach to shared memory.	This message will only be seen if the watchdog is started on a machine directly (ie: not as a result of starting SLEE). No resolution.	ACS
110837	INFO	SLEE[%d]: slee_acs(%d) INFO: Starting Interface %s %d FAILED :%z	The specified interface has failed to start.	Refer to application expert first. (Check the following). 1) Check SLEE config (SLEE.cfg) 2) Check binary is exists, permissions are correct and is not corrupt. Finally contact support.	ACS
110838	ERROR	SLEE[%d]: slee_acs(%d) ERROR: Applicaton %s %d does not exist at PID %d, presuming dead.	The specified application has died/finished, the watchdog will attempt to restart it.	Refer to application expert first. Ensure that the application has restarted correctly (observe syslog). Finally contact support.	ACS
110839	ERROR	SLEE[%d]: slee_acs(%d) ERROR: Interface %s %d does not exist at PID %d, presuming dead.	The specified interface has died/finished, the watchdog will attempt to restart it.	Refer to application expert first. Ensure that the interface has restarted correctly (observe syslog). Finally contact support.	ACS
110840	CRITICAL	SLEE[%d]: slee_acs(%d) CRITICAL: Too many processes (%d != 1) attached to shared memory	There are too many processes attached to the SLEE shared memory.	Refer to application expert. 1) Stop SLEE, change kernel parameters as per installation guide. 2) Clean shared memory 3) Start SLEE. Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110841	ERROR	SLEE[%d]: slee_acs(%d) ERROR: Watchdog error too many processes attached to shared memory	There are too many processes attached to the SLEE shared memory.	Refer to application expert. 1) Stop SLEE, change kernel parameters as per installation guide. 2) Clean shared memory 3) Start SLEE. Finally contact support.	ACS
110842	CRITICAL	SLEE[%d]: slee_acs(%d) CRITICAL: Error restarting the SLEE (exec slee.sh) -%z	The watchdog can not automatically restart SLEE.	Refer to application expert. 1) Stop SLEE. 2) Clean shared memory. 3) Start SLEE. Finally contact support.	ACS
110843	CRITICAL	SLEE[%d]: slee_acs(%d) CRITICAL: Error getting shared memory -%z	The watchdog process can not detach from shared memory. This message will only be seen if the SLEE shared memory has become corrupt.	Stop SLEE, clean shared memory, start SLEE	ACS
110844	CRITICAL	SLEE[%d]: slee_acs(%d) CRITICAL: Error marking shared memory -%z	The watchdog process can not detach from shared memory. This message will only be seen if the SLEE shared memory has become corrupt.	Stop SLEE, clean shared memory, start SLEE	ACS
110845	ERROR	SLEE[%d]: slee_acs(%d) ERROR: Watchdog error getting shared memory information : Error %d	The watchdog process can not detach from shared memory. This message will only be seen if the SLEE shared memory has become corrupt.	Stop SLEE, clean shared memory, start SLEE	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110846	CRITICAL	SLEE[%d]: slee_acs(%d) CRITICAL: Error detaching shared memory - %z	The watchdog process can not detach from shared memory. This message will only be seen if the SLEE shared memory has become corrupt.	Stop SLEE, clean shared memory, start SLEE	ACS
110847	NOTICE	SLEE[%d]: slee_acs(%d) ERROR: Call ID %d	An internal error has occurred.	No resolution.	ACS
110848	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE: (%s %d,%s %d,%s %d,%s %d,%s %d)	Information only.	No resolution	ACS
110849	CRITICAL	SLEE[%d]: slee_acs(%d) CRITICAL =%d SinapTcSccpInterface.cc@%d: SINAP not initialised	SINAP did not initialise properly.	Refer to application expert. Check SINAP configuration then call support	ACS
110850	CRITICAL	SLEE[%d]: slee_acs(%d) CRITICAL =%d SinapTcSccpInterface.cc@%d: Encoded SCCP data too long at %d bytes	TCAP stack serious internal error.	Contact support	ACS
110851	WARNING	SLEE[%d]: slee_acs(%d) WARNING =%d SinapTcSccpInterface.cc@%d: TCAP reject: %s %d of type %s %d code %d specifier %d	Applications request to send TCAP message was rejected by TCAP stack for the reason specified.	Contact signalling/network support.	ACS
110852	WARNING	SLEE[%d]: slee_acs(%d) WARNING =%d SinapTcSccpInterface.cc@%d: SCMG: PC-STATE pc=%d congested at %d	The specified point code is congested.	No resolution. Requires no action on platform.	ACS
110853	WARNING	SLEE[%d]: slee_acs(%d) WARNING =%d SinapTcSccpInterface.cc@%d: SCMG: PC-STATE pc=%d %s %d	PC State indication.	No resolution. Requires no action on platform.	ACS
110854	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE =%d SinapTcSccpInterface.cc@%d: SCMG: N-STATE pc=%d, ssn=%d, multi=%d %z	SCCP N-State indication.	No resolution. Requires no action on platform.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110855	WARNING	SLEE[%d]: slee_acs(%d) WARNING =%d SinapTcSccpInterface.cc@%d: TCAP reject: %s %d	TCAP reject received.	No resolution. Requires no action on platform.	ACS
110856	WARNING	SLEE[%d]: slee_acs(%d) WARNING =%d SinapTcSccpInterface.cc@%d: Unknown SINAP SCCP message 0x%s %d	SINAP sent an unknown SCCP message to TCAP stack.	Refer to application/signalling expert. May indicate a mismatch in version between SINAP and TCAP interface. Contact support.	ACS
110857	WARNING	%z Received unknown IPC message %d	Unknown SINAP IPC message received.	Refer to application/signalling expert. May indicate a mismatch in version between SINAP and TCAP interface. Contact support.	ACS
110858	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE =%d SinapTcSccpInterface.cc@%d: Local SSN %d Out of service	The specified local SCCP subsystem has come into service.	No resolution. Requires no action on platform.	ACS
110859	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE =%d SinapTcSccpInterface.cc@%d: Local SSN %d In service	The specified local SCCP subsystem has gone out of service.	No resolution. Requires no action on platform.	ACS
110860	ERROR	SLEE[%d]: slee_acs(%d) ERROR =%d SinapTcSccpInterface.cc@%d: SINAP ERROR from ca_alloc_tc() errno=%d	SINAP TCAP error.	Refer to application expert. Explore SINAP documentation.	ACS
110861	ERROR	SLEE[%d]: slee_acs(%d) ERROR =%d SinapTcSccpInterface.cc@%d: SINAP ERROR %s %d	SINAP general error.	Refer to application expert. Explore SINAP documentation.	ACS
110862	CRITICAL	SLEE[%d]: slee_acs(%d) CRITICAL =%d SinapTcSccpInterface.cc@%d: SINAP Internal problemZZZ	SINAP general error.	Refer to application expert. Explore SINAP documentation.	ACS
110863	ERROR	SLEE[%d]: slee_acs(%d) ERROR =%d SinapTcSccpInterface.cc@%d: SINAP ERROR from ca_get_tc() errno=%d	SINAP TCAP error.	Refer to application expert. Explore SINAP documentation (note error 4017 commonly identifies SCCP level routing problem/misconfiguration).	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110864	ERROR	SLEE[%d]: slee_acs(%d) ERROR =%d SinapTcSccpInterface.cc@%d: SINAP ERROR from ca_put_tc() errno=%d for prim %d	SINAP TCAP error.	Refer to application expert. Explore SINAP documentation (note error 4017 commonly identifies SCCP level routing problem/misconfiguration).	ACS
110865	WARNING	SLEE[%d]: slee_acs(%d) WARNING =%d SinapTcSccpInterface.cc@%d: SINAP ERROR from ca_get_msg() errno=%d	SINAP TCAP error.	Refer to application expert. Explore SINAP documentation.	ACS
110866	WARNING	SLEE[%d]: slee_acs(%d) WARNING =%d SinapTcSccpInterface.cc@%d: Received signal for pf_begin	SINAP power failure indication.	Refer to application expert. Restore interrupted power and restart interface.	ACS
110867	WARNING	SLEE[%d]: slee_acs(%d) WARNING =%d SinapTcSccpInterface.cc@%d: Received signal for pf_ridethru	SINAP power failure issue cleared.	No resolution. Requires no action on platform.	ACS
110868	ERROR	SLEE[%d]: slee_acs(%d) ERROR =%d SinapTcSccpInterface.cc@%d: SINAP Route to PC %d(%s %d) not provisioned	MTP route to indicated Point Code destination is not provisioned within SINAP.	Use SINAP sysopr management system to configure MTP route to the indicated destination.	ACS
110869	CRITICAL	SLEE[%d]: slee_acs(%d) CRITICAL =%d SinapTcSccpInterface.cc@%d: SINAP ERROR RECV, %d-shmat error (PSYSTEM)	SINAP general error.	Refer to application expert. Explore SINAP documentation.	ACS
110870	ERROR	%z TSM received undefined event %s %d in state %s %d	TCAP stack received an unexpected event.	Contact signalling/network support.	ACS
110871	ERROR	%z DHA received undefined event %s %d in state %s %d	TCAP stack received an unexpected event.	Contact signalling/network support.	ACS
110872	ERROR	%z ISM received undefined event %s %d in state %s %d	TCAP stack received a Return Result/Error message for an invoke that did not expect one.	Refer to application/signalling expert. Reduce rate of queries from network into application on this interface.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110873	CRITICAL	SLEE[%d]: slee_acs(%d) CRITICAL =%d TcSccpCommonInterface.cc@%d: Encoded SCCP data too long at 123bytes	TCAP stack serious internal error.	Contact support	ACS
110874	ERROR	%z Unsupported event %z	TCAP received an unsupported message.	Contact signalling/network support.	ACS
110875	CRITICAL	%z Failed to send TCTR N- UNITDATA message for %z	TCAP stack failed to send TR-UNI to underlying stack.	Contact signalling/network support.	ACS
110876	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE =%d TcSccpCommonInterface.cc@%d: SCMG: N-STATE pc=%d, ssn=%d, multi=%d out of service	The specified subsystem at the specified point code has gone out of service.	No resolution. Requires no action on platform.	ACS
110877	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE =%d TcSccpCommonInterface.cc@%d: SCMG: N-STATE pc=%d, ssn=%d, multi=%d in service	The specified subsystem at the specified point code has come into service.	No resolution. Requires no action on platform.	ACS
110878	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE =%d TcSccpCommonInterface.cc@%d: SCMG: PC-STATE pc=%d inaccessible STP	The specified STP has become inaccessible.	No resolution. Requires no action on platform.	ACS
110879	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE =%d TcSccpCommonInterface.cc@%d: SCMG: PC-STATE pc=%d accessible STP	The specified STP has become accessible.	No resolution. Requires no action on platform.	ACS
110880	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE =%d TcSccpCommonInterface.cc@%d: SCMG: PC-STATE pc=%d inaccessible	The specified point code has become inaccessible.	No resolution. Requires no action on platform.	ACS
110881	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE =%d TcSccpCommonInterface.cc@%d: SCMG: PC-STATE pc=%d accessible	The specified point code has become accessible.	No resolution. Requires no action on platform.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110882	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE =%d TcSccpCommonInterface.cc@%d: SCMG: N-STATE pc=%d, ssn=%d, multi=%d unknown status	The specified subsystem at the specified point code sent an unrecognised N-STATE message.	Refer to application/signalling expert. Reduce rate of queries from network into application on this interface.	ACS
110883	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE =%d TcSccpCommonInterface.cc@%d: SCMG: PC-STATE pc=%d unknown status	The specified point code sent an unrecognised PC-STATE message.	Refer to application/signalling expert. Reduce rate of queries from network into application on this interface.	ACS
110884	ERROR	%z Unrecognised Transaction ID received (%d)	TCAP stack received a message from the network on a dialogue (transaction) it does not recognise.	Refer to application/signalling expert. Reduce rate of queries from network into application on this interface.	ACS
110885	ERROR	%z Unrecognised Dialogue ID received (%d)	TCAP stack received a message from the network on a dialogue (transaction) it does not recognise.	Refer to application/signalling expert. Reduce rate of queries from network into application on this interface.	ACS
110886	ERROR	%z Component type %d not handled	TCAP stack received an Invalid TCAP message from network.	Refer to application/signalling expert. Reduce rate of queries from network into application on this interface.	ACS
110887	ERROR	%z Primitive type %d not handled	TCAP stack received an Invalid TCAP message from network.	Refer to application/signalling expert. Reduce rate of queries from network into application on this interface.	ACS
110888	ERROR	%z Run out of outgoing dialogue ids	TCAP stack has run out of TCAP dialogues.	Refer to application/signalling expert. Restart interface with increased dialogues (MAXDIDS parameter).	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110889	ERROR	%z Run out of TCAP transaction/dialogue IDs	TCAP stack has run out of TCAP dialogues.	Refer to application/signalling expert. Restart interface with increased dialogues (MAXDIDS parameter).	ACS
110890	WARNING	%z Failed to process invoke id %d (already in use?)	Application attempted to re-use a TCAP invoke ID that was already in use for that transaction.	Contact support.	ACS
110891	WARNING	SLEE[%d]: slee_acs(%d) WARNING =%d TcSccpCommonInterface.cc@%d: SCMG: PC-STATE pc=%d congested at %d	The specified point code is congested.	No resolution. Requires no action on platform.	ACS
110892	WARNING	SLEE[%d]: slee_acs(%d) WARNING =%d TcSccpCommonInterface.cc@%d: Recevied unkown IPC message %d	SINAP sent an unknown internal message.	Refer to application/signalling expert. May indicate a mismatch in version between SINAP and TCAP interface. Contact support.	ACS
110893	ERROR	SLEE[%d]: slee_acs(%d) ERROR =%d TcSccpCommonInterface.cc@%d: Reject for non-active ISM	TCAP stack Invoke State Machine violation.	Contact signalling/network support.	ACS
110894	ERROR	%z TCAP syntax error %z	TCAP stack received a error message from the network for an invoke that did not expect one.	Refer to application/signalling expert. Reduce rate of queries from network into application on this interface.	ACS
110895	ERROR	SLEE[%d]: slee_acs(%d) ERROR =%d TcapTransaction.cc@%d: TSM received undefined event %s %d in state %s %d	TCAP stack received an unexpected event.	Contact signalling/network support.	ACS
110896	ERROR	SLEE[%d]: slee_acs(%d) ERROR =%d TcapTransaction.cc@%d: DHA received undefined event %s %d in state %s %d	TCAP stack received an unexpected event.	Contact signalling/network support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110897	NOTICE	%z Our message was rejected, but unexpected invoke id %d (timed out?)	TCAP stack received an Invalid TCAP message from network.	Refer to application/signalling expert. Reduce rate of queries from network into application on this interface.	SLEE_TC
110898	CRITICAL	SLEE[%d]: slee_acs(%d) CRITICAL =%d TcapTransaction.cc@%d: Encoded SCCP data too long at 123bytes	TCAP stack serious internal error.	Contact support	ACS
110899	ERROR	SLEE[%d]: slee_acs(%d) ERROR =%d TcapTransaction.cc@%d: Unsupported eventZZZ	TCAP received an unsupported message.	Contact signalling/network support.	ACS
110900	CRITICAL	SLEE[%d]: slee_acs(%d) CRITICAL =%d TcapTransaction.cc@%d: Failed to send TCTR N-UNITDATA message forZZZ	TCAP stack failed to send TR-UNI to underlying stack.	Contact signalling/network support.	ACS
110901	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE =%d TcapTransaction.cc@%d: SCMG: N-STATE pc=%d, ssn=%d, multi=%d in service	The specified subsystem at the specified point code has come into service.	No resolution. Requires no action on platform.	ACS
110902	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE =%d TcapTransaction.cc@%d: SCMG: N-STATE pc=%d, ssn=%d, multi=%d out of service	The specified subsystem at the specified point code has gone out of service.	No resolution. Requires no action on platform.	ACS
110903	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE =%d TcapTransaction.cc@%d: SCMG: PC-STATE pc=%d inaccessible STP	The specified STP has become inaccessible.	No resolution. Requires no action on platform.	ACS
110904	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE =%d TcapTransaction.cc@%d: SCMG: PC-STATE pc=%d accessible STP	The specified STP has become accessible.	No resolution. Requires no action on platform.	ACS
110905	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE =%d TcapTransaction.cc@%d: SCMG: PC-STATE pc=%d inaccessible	The specified point code has become inaccessible.	No resolution. Requires no action on platform.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110906	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE =%d TcapTransaction.cc@%d: SCMG: PC-STATE pc=%d accessible	The specified point code has become accessible.	No resolution. Requires no action on platform.	ACS
110907	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE =%d TcapTransaction.cc@%d: SCMG: N-STATE pc=%d, ssn=%d, multi=%d unknown status	The specified subsystem at the specified point code sent an unrecognised N-STATE message.	Refer to application/signalling expert. Reduce rate of queries from network into application on this interface.	ACS
110908	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE =%d TcapTransaction.cc@%d: SCMG: PC-STATE pc=%d unknown status	The specified point code sent an unrecognised PC- STATE message.	Refer to application/signalling expert. Reduce rate of queries from network into application on this interface.	ACS
110909	ERROR	SLEE[%d]: slee_acs(%d) ERROR =%d TcapTransaction.cc@%d: Unrecognised Transaction ID received (%d)	TCAP stack received a message from the network on a dialogue (transaction) it does not recognise.	Refer to application/signalling expert. Reduce rate of queries from network into application on this interface.	ACS
110910	ERROR	SLEE[%d]: slee_acs(%d) ERROR =%d TcapTransaction.cc@%d: Unrecognised Dialogue ID received (%d)	TCAP stack received a message from the network on a dialogue (transaction) it does not recognise.	Refer to application/signalling expert. Reduce rate of queries from network into application on this interface.	ACS
110911	ERROR	SLEE[%d]: slee_acs(%d) ERROR =%d TcapTransaction.cc@%d: Component type %d not handled	TCAP stack received an Invalid TCAP message from network.	Refer to application/signalling expert. Reduce rate of queries from network into application on this interface.	ACS
110912	ERROR	SLEE[%d]: slee_acs(%d) ERROR =%d TcapTransaction.cc@%d: Primitive type %d not handled	TCAP stack received an Invalid TCAP message from network.	Refer to application/signalling expert. Reduce rate of queries from network into application on this interface.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110913	ERROR	SLEE[%d]: slee_acs(%d) ERROR =%d TcapTransaction.cc@%d: Run out of outgoing dialogue ids	TCAP stack has run out of TCAP dialogues.	Refer to application/signalling expert. Restart interface with increased dialogues (MAXDIDS parameter).	ACS
110914	ERROR	SLEE[%d]: slee_acs(%d) ERROR =%d TcapTransaction.cc@%d: Run out of TCAP transaction/dialogue IDs	TCAP stack has run out of TCAP dialogues.	Refer to application/signalling expert. Restart interface with increased dialogues (MAXDIDS parameter).	ACS
110915	WARNING	SLEE[%d]: slee_acs(%d) WARNING =%d TcapTransaction.cc@%d: Failed to process invoke id %d (already in use?)	Application attempted to re-use a TCAP invoke ID that was already in use for that transaction.	Contact support.	ACS
110916	WARNING	SLEE[%d]: slee_acs(%d) WARNING =%d TcapTransaction.cc@%d: SCMG: PC-STATE pc=%d congested at %d	The specified point code is congested.	No resolution. Requires no action on platform.	ACS
110917	WARNING	SLEE[%d]: slee_acs(%d) WARNING =%d TcapTransaction.cc@%d: Received unknown IPC message %d	SINAP sent an unknown internal message.	Refer to application/signalling expert. May indicate a mismatch in version between SINAP and TCAP interface. Contact support.	ACS
110918	ERROR	SLEE[%d]: slee_acs(%d) ERROR =%d TcapTransaction.cc@%d: Reject for non-active ISM	TCAP stack Invoke State Machine violation.	Contact signalling/network support.	ACS
110919	ERROR	SLEE[%d]: slee_acs(%d) ERROR =%d TcapTransaction.cc@%d: TCAP syntax errorZZZ	TCAP stack received a error message from the network for an invoke that did not expect one.	Refer to application/signalling expert. Reduce rate of queries from network into application on this interface.	ACS
110920	ERROR	SLEE[%d]: slee_acs(%d) ERROR =%d sleeTcapIf.cc@%d: TC primitive received without any components	A TC-BEGIN from the network was received with no TC--INVOKE component contained within it.	Refer to application/signalling expert. Suspected SSP misconfiguration.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110921	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE =%d sleeTcapIf.cc@%d: Rejected %d calls out of %d in the last 30s	Calling attempt rate from network into the interface has exceeded the configured threshold and the indicated number of calls were rejected. because of this	Refer to application/signalling expert. Reduce rate of queries from network into application on this interface.	ACS
110922	CRITICAL	SLEE[%d]: slee_acs(%d) CRITICAL =%d sleeTcapIf.cc@%d: Unknown service key %s %d	Applications request to send TCAP message was rejected by TCAP stack for the reason specified.	Contact signalling/network support.	ACS
110923	ERROR	SLEE[%d]: slee_acs(%d) ERROR =%d sleeTcapIf.cc@%d: TC_BEGIN with no IDP/ARI (got %d.%d)	A TC-BEGIN from the network was received by an INAP handling i/f that did not contain an IDP nor ARI TC--INVOKE component.	Refer to application/signalling expert. Check interface configurred against the SSN for INAP if so contact signalling/network support.	ACS
110924	ERROR	SLEE[%d]: slee_acs(%d) ERROR =%d sleeTcapIf.cc@%d: Unknown correlation id %d	Interface attempted to commence a dialogue with the SLEE with the specified service key which is not configured in the SLEE.	Refer to application expert. Configure the displayed service key in SLEEs configuration file (SLEE.cfg)	ACS
110925	CRITICAL	SLEE[%d]: slee_acs(%d) ERROR =%d sleeTcapIf.cc@%d: Conveyed protocol %d not supported by Slee Tcap i/f	Interface attempted to commence a dialogue with the SLEE with the unknown protocol.	Contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110926	CRITICAL	SLEE[%d]: slee_acs(%d) CRITICAL =%d SinapTcapInterface.cc@%d: SINAP not initialised	SINAP did not initialise properly.	Refer to application expert. Check SINAP configuration then call support	ACS
110927	CRITICAL	SLEE[%d]: slee_acs(%d) CRITICAL =%d SinapTcapInterface.cc@%d: Encoded SCCP data too long at %d bytes	TCAP stack serious internal error.	Contact support	ACS
110928	WARNING	SLEE[%d]: slee_acs(%d) WARNING =%d SinapTcapInterface.cc@%d: TCAP reject: %s %d of type %s %d code %d specifier %d	Applications request to send TCAP message was rejected by TCAP stack for the reason specified.	Contact support.	ACS
110929	WARNING	SLEE[%d]: slee_acs(%d) WARNING =%d SinapTcapInterface.cc@%d: SCMG: PC-STATE pc=%d congested at %d	The specified point code is congested.	No resolution. Requires no action on platform.	ACS
110930	WARNING	SLEE[%d]: slee_acs(%d) WARNING =%d SinapTcapInterface.cc@%d: SCMG: PC-STATE pc=%d %s %d	PC State indication.	No resolution. Requires no action on platform.	ACS
110931	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE =%d SinapTcapInterface.cc@%d: SCMG: N-STATE pc=%d, ssn=%d, multi=%d %z	SCCP N-State indication.	No resolution. Requires no action on platform.	ACS
110932	WARNING	SLEE[%d]: slee_acs(%d) WARNING =%d SinapTcapInterface.cc@%d: TCAP reject: %s %d	TCAP reject received.	No resolution. Requires no action on platform.	ACS
110933	WARNING	SLEE[%d]: slee_acs(%d) WARNING =%d SinapTcapInterface.cc@%d: Unknown SINAP SCCP message 0x%s %d	SINAP sent an unknown SCCP message to TCAP stack.	Refer to application/signalling expert. May indicate a mismatch in version between SINAP and TCAP interface. Contact support.	ACS
110934	WARNING	SLEE[%d]: slee_acs(%d) WARNING =%d SinapTcapInterface.cc@%d: Receieved unkown IPC message %d	Unknown SINAP IPC message received.	Refer to application/signalling expert. May indicate a mismatch in version between SINAP and TCAP interface. Contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110935	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE =%d SinapTcapInterface.cc@%d: Local SSN %d Out of service	The specified local SCCP subsystem has come into service.	No resolution. Requires no action on platform.	ACS
110936	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE =%d SinapTcapInterface.cc@%d: Local SSN %d In service	The specified local SCCP subsystem has gone out of service.	No resolution. Requires no action on platform.	ACS
110937	ERROR	SLEE[%d]: slee_acs(%d) ERROR =%d SinapTcapInterface.cc@%d: SINAP ERROR from ca_alloc_tc() errno=%d	SINAP TCAP error.	Refer to application expert. Explore SINAP documentation.	ACS
110938	ERROR	SLEE[%d]: slee_acs(%d) ERROR =%d SinapTcapInterface.cc@%d: SINAP ERROR %s %d	SINAP general error.	Refer to application expert. Explore SINAP documentation.	ACS
110939	CRITICAL	SLEE[%d]: slee_acs(%d) CRITICAL =%d SinapTcapInterface.cc@%d: SINAP Internal problemZZZ	SINAP general error.	Refer to application expert. Explore SINAP documentation.	ACS
110940	ERROR	SLEE[%d]: slee_acs(%d) ERROR =%d SinapTcapInterface.cc@%d: SINAP ERROR from ca_get_tc() errno=%d	SINAP TCAP error.	Refer to application expert. Explore SINAP documentation (note error 4017 commonly identifies SCCP level routing problem/misconfiguration).	ACS
110941	ERROR	SLEE[%d]: slee_acs(%d) ERROR =%d SinapTcapInterface.cc@%d: SINAP ERROR from ca_put_tc() errno=%d for prim %d	SINAP TCAP error.	Refer to application expert. Explore SINAP documentation (note error 4017 commonly identifies SCCP level routing problem/misconfiguration).	ACS
110942	WARNING	SLEE[%d]: slee_acs(%d) WARNING =%d SinapTcapInterface.cc@%d: SINAP ERROR from ca_get_msg() errno=%d	SINAP TCAP error.	Refer to application expert. Explore SINAP documentation.	ACS
110943	WARNING	SLEE[%d]: slee_acs(%d) WARNING =%d SinapTcapInterface.cc@%d: Received signal for pf_begin	SINAP power failure indication.	Refer to application expert. Restore interrupted power and restart interface.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110944	WARNING	SLEE[%d]: slee_acs(%d) WARNING =%d SinapTcapInterface.cc@%d: Received signal for pf_ridethru	SINAP power failure issue cleared.	No resolution. Requires no action on platform.	ACS
110945	ERROR	SLEE[%d]: slee_acs(%d) ERROR =%d SinapTcapInterface.cc@%d: SINAP Route to PC %d(%s %d) not provisioned	MTP route to indicated Point Code destination is not provisioned within SINAP.	Use SINAP sysopr management system to configure MTP route to the indicated destination.	ACS
110946	CRITICAL	SLEE[%d]: slee_acs(%d) CRITICAL =%d SinapTcapInterface.cc@%d: SINAP ERROR RECV, %d-shmat error (PSYSTEM)	SINAP general error.	Refer to application expert. Explore SINAP documentation.	ACS
110947	WARNING	SLEE[%d]: slee_acs(%d) WARNING acsSLEEChassis_t::callEngine=0 acsChassis.cc@%d: , line 0:Memory Allocation Error	ACS Chassis raised an unexpected event.	Contact support.	ACS
110948	WARNING	SLEE[%d]: slee_acs(%d) WARNING acsSLEEChassis_t::callEngine=0 acsChassis.cc@%d: absReadSecretNode.cc, line %d:ReadSecretCode: Invalid message recieved	ACS Chassis raised an unexpected event.	Contact support.	ACS
110949	WARNING	SLEE[%d]: slee_acs(%d) WARNING acsSLEEChassis_t::callEngine=0 acsChassis.cc@%d: VoucherRecharge.c, line %d:Invalid Status received from Chassis	ACS Chassis raised an unexpected event.	Contact support.	ACS
110950	WARNING	SLEE[%d]: slee_acs(%d) WARNING acsSLEEChassis_t::callEngine=0 acsChassis.cc@%d: VoucherRecharge.c, line %d:VoucherRecharge: unknown reason for decline	ACS Chassis raised an unexpected event.	Contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110956	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR: ORA123: Cant modify control plan structure with build != B	After compiling a control plan an Oracle object fails.	Refer to Oracle/application expert first. Establish object, identify invalid data and contact support.	ACS
110957	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR: ORA123: deadlock detected while waiting for resource	Oracle internal error.	Contact support.	ACS
110958	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR: ORA123: existing state of packages has been discarded	Internal error.	No resolution.	ACS
110959	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR: ORA123: integrity constraint (%s %d) violated - child record found	After compiling a control plan an Oracle object fails.	Refer to Oracle/application expert first. Establish object, identify invalid data and contact support.	ACS
110960	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR: ORA123: no data found	Control plan does not exist.	Refer to application expert. Check content of the ACS_COMPILE_LIST table. This has a reference to a control plan that no longer exists. Delete entry if necessary.	ACS
110961	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR: ORA123: trigger %s %d is invalid and failed re-validation	After compiling a control plan an Oracle object fails.	Refer to Oracle/application expert first. Establish object, identify invalid data and contact support.	ACS
110962	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR: ORA123: unable to extend index %s %d by %d in tablespace %s %d	Out of disk space.	Refer to Oracle expert. Free some disk space to allow the tablespace to be extended.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110963	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR: ORACLE error--	Oracle internal error.	Refer to ORACLE/application expert first (Check the following). 1) Verify that ORACLE is running through checking the status of the listener(lsnrctl) and restart ORACLE only if necessary. 2) Check the environment variables and/or configuration files: ORACLE_SID(environment), tnsnames.ora(configuration file), listener.ora(configuration file). 3) Verify that the username and password for the current machine is correct. 4) Observe startup output for errors. Finally contact support.	ACS
110964	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR: Unable to connect to Oracle	Cannot connect to ORACLE.	Refer to ORACLE/application expert first (Check the following). 1) Verify that ORACLE is running through checking the status of the listener(lsnrctl) and restart ORACLE only if necessary. 2) Check the environment variables and/or configuration files: ORACLE_SID(environment), tnsnames.ora(configuration file), listener.ora(configuration file). 3) Verify that the username and password for the current machine is correct. 4) Observe startup output for errors. Finally contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110965	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR: Unable to get compiled structure	Control plan does not exist.	Refer to application expert. Check content of the ACS_COMPILE_LIST table. This has a reference to a control plan that no longer exists. Delete entry if necessary.	ACS
110966	NOTICE	acsCompilerDaemon: acsCompilerDaemon(%d) NOTICE: acsCompilerDaemon: COMPRESS_AT_KB = %d	Information only.	No resolution.	ACS
110967	NOTICE	acsCompilerDaemon: acsCompilerDaemon(%d) NOTICE: acsCompilerDaemon: CONFIG_DIR =%z	Information only.	No resolution.	ACS
110968	NOTICE	acsCompilerDaemon: acsCompilerDaemon(%d) NOTICE: acsCompilerDaemon: CONFIG_FILE =%z	Information only.	No resolution.	ACS
110969	NOTICE	acsCompilerDaemon: acsCompilerDaemon(%d) NOTICE: acsCompilerDaemon: CONFIG_SECTION =%z	Information only.	No resolution.	ACS
110970	NOTICE	acsCompilerDaemon: acsCompilerDaemon(%d) NOTICE: acsCompilerDaemon: END_UNLINKED_EXITS = %d	Information only.	No resolution.	ACS
110971	NOTICE	acsCompilerDaemon: acsCompilerDaemon(%d) NOTICE: acsCompilerDaemon: MAX_BRANCHES = %d	Information only.	No resolution.	ACS
110972	NOTICE	acsCompilerDaemon: acsCompilerDaemon(%d) NOTICE: acsCompilerDaemon: MAX_COMPILED_KB = %d	Information only.	No resolution.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110973	NOTICE	acsCompilerDaemon: acsCompilerDaemon(%d) NOTICE: acsCompilerDaemon: MAX_NODES = %d	Information only.	No resolution.	ACS
110974	NOTICE	acsCompilerDaemon: acsCompilerDaemon(%d) NOTICE: acsCompilerDaemon: TIMEOUT = %d	Information only.	No resolution.	ACS
110975	ERROR	acsProfileCompiler: acsProfileCompiler(%d) ERROR main=%d acsProfileCompiler.cc@%d: Unable to connect to Oracle	Cannot connect to ORACLE.	Refer to ORACLE/application expert first (Check the following). 1) Verify that ORACLE is running through checking the status of the listener(lsnrctl) and restart ORACLE only if necessary. 2) Check the environment variables and/or configuration files: ORACLE_SID(environment), tnsnames.ora(configuration file), listener.ora(configuration file). 3) Verify that the username and password for the current machine is correct. 4) Observe startup output for errors. Finally contact support.	ACS
110976	ERROR	acsProfileCompiler: acsProfileCompiler(%d) ERROR: CustomerTNRRangeCompiler::isCompi leNeeded():SELECT FROM %s %d : ORA123: not logged on	Oracle internal error.	Contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110977	ERROR	acsProfileCompiler: acsProfileCompiler(%d) ERROR: DefaultTNRangeCompiler::isCompileNeeded():SELECT FROM ACS_GLOBAL_PROFILE : ORA123: unable to allocate %d bytes of shared memoryZZZ	Error writing to shared memory.	Contact support.	ACS
110978	ERROR	acsProfileCompiler: acsProfileCompiler(%d) ERROR: Error locking record (%s %d)	Oracle internal error.	Contact support.	ACS
110979	ERROR	acsProfileCompiler: acsProfileCompiler(%d) ERROR: Failed to connect to oracle as userZZZ	Cannot connect to ORACLE.	Refer to ORACLE/application expert first (Check the following). 1) Verify that ORACLE is running through checking the status of the listener(lsnrctl) and restart ORACLE only if necessary. 2) Check the environment variables and/or configuration files: ORACLE_SID(environment), tnsnames.ora(configuration file), listener.ora(configuration file). 3) Verify that the username and password for the current machine is correct. 4) Observe startup output for errors. Finally contact support.	ACS
110980	NOTICE	acsProfileCompiler: acsProfileCompiler(%d) NOTICE: cmnConfigGetFlag: AuditChallenge not found (use default)	Config item not found. Using default.	No resolution.	ACS
110981	NOTICE	acsProfileCompiler: acsProfileCompiler(%d) NOTICE: cmnConfigGetFlag: AuditChallenge setZZZ	Information only.	No resolution.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110982	NOTICE	acsProfileCompiler: acsProfileCompiler(%d) NOTICE: cmnConfigGetString: oraclepassword not found (use default)	Config item not found. Using default.	No resolution.	ACS
110983	NOTICE	acsProfileCompiler: acsProfileCompiler(%d) NOTICE: cmnConfigGetString: oraclepassword setZZZ	Information only.	No resolution.	ACS
110984	NOTICE	acsProfileCompiler: acsProfileCompiler(%d) NOTICE: cmnConfigGetString: oracleusername not found (use default)	Config item not found. Using default.	No resolution.	ACS
110985	NOTICE	acsProfileCompiler: acsProfileCompiler(%d) NOTICE: cmnConfigGetString: oracleusername setZZZ	Information only.	No resolution.	ACS
110986	CRITICAL	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) CRITICAL: Cannot connect to host %s %d -%z	Cannot connect to remote host.	Refer to application expert. Check all nodes are operational and verify connectivity.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110987	CRITICAL	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) CRITICAL: Cannot connect to Oracle	Cannot connect to ORACLE.	Refer to ORACLE/application expert first (Check the following). 1) Verify that ORACLE is running through checking the status of the listener(lsnrctl) and restart ORACLE only if necessary. 2) Check the environment variables and/or configuration files: ORACLE_SID(environment), tnsnames.ora(configuration file), listener.ora(configuration file). 3) Verify that the username and password for the current machine is correct. 4) Observe startup output for errors. Finally contact support.	ACS
110988	CRITICAL	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) CRITICAL: Send/Request failed. Exiting.	Cannot connect to remote host.	Refer to application expert. Check all nodes are operational and verify connectivity.	ACS
110989	ERROR	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) ERROR: Cannot Recv -%z	Cannot connect to remote host.	Refer to application expert. Check all nodes are operational and verify connectivity.	ACS
110990	NOTICE	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) NOTICE: Connecting to host %s %d port %d	Attempting to contact stats master.	No resolution.	ACS
110991	CRITICAL	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) CRITICAL SleeException=%d sleeError.cc@%d:%z	Exception raised from SLEE.	Contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
110992	NOTICE	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) NOTICE: Terminating on SLEE Kill Message	Process has been killed.	No resolution.	ACS
110993	NOTICE	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) NOTICE: Startup Successful	Information only.	No resolution.	ACS
110994	ERROR	acsStatsMaster: acsStatsMaster(%d) ERROR: Out of space for holding Child PID	Out of disk space.	Refer to application/UNIX expert. Remove unnecessary files.	ACS
110995	ERROR	acsStatsMaster: acsStatsMaster(%d) ERROR: Read %d byte client request, expected %d	Data communication inconsistency.	No resolution.	ACS
110996	NOTICE	acsStatsMaster: acsStatsMaster(%d) NOTICE: Bind/Listen to port %d	Information only.	No resolution.	ACS
110997	NOTICE	acsStatsMaster: acsStatsMaster(%d) NOTICE: Connection ended for process %d	Connection has ended to remote node.	No resolution.	ACS
110998	NOTICE	acsStatsMaster: acsStatsMaster(%d) NOTICE: Forked server process %d	Information only.	No resolution.	ACS
110999	NOTICE	acsStatsMaster: acsStatsMaster(%d) NOTICE: Setup signal handlers	Setting up signal handlers.	No resolution.	ACS
111000	NOTICE	acsStatsMaster: acsStatsMaster(%d) NOTICE: Shutting Down	acsStatsMaster is shutting down.	Contact support.	ACS
111001	NOTICE	acsStatsMaster: acsStatsMaster(%d) NOTICE: Startup Successfull	Information only.	No resolution.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
111002	NOTICE	acsStatsMaster: acsStatsMaster(%d) NOTICE: Terminating child [%d] PID %d	Killing child process.	No resolution.	ACS
111003	CRITICAL	SLEE[%d]: slee_acs(%d) CRITICAL SleeApplication::new()=%d sleeApplication.cc@%d: No available applications	Cannot process application.	Refer to application expert. Increase MAXAPPLICATIONS in SLEE.cfg.	ACS
111004	CRITICAL	SLEE[%d]: slee_acs(%d) CRITICAL SleeCallInstance::new()=%d sleeCallInstance.cc@%d: No available call instances	Cannot process call.	Refer to application expert. Increase MAXCALLS in SLEE.cfg.	ACS
111005	CRITICAL	SLEE[%d]: slee_acs(%d) CRITICAL SleeDialog::new()=%d sleeDialog.cc@%d: No available dialogs	Cannot process dialog.	Refer to application expert. Increase MAXDIALOGS in SLEE.cfg.	ACS
111006	CRITICAL	SLEE[%d]: slee_acs(%d) CRITICAL SleeEvent::new()=%d sleeEvent.cc@%d: No available events	Cannot process event.	Refer to application expert. Increase MAXEVENTS in SLEE.cfg.	ACS
111007	CRITICAL	SLEE[%d]: slee_acs(%d) CRITICAL SleeEvent::validateEvent()=%d sleeEvent.cc@%d:%z	Exception raised from SLEE.	Contact support.	ACS
111008	CRITICAL	SLEE[%d]: slee_acs(%d) CRITICAL SleeEventType::new()=%d sleeEventType.cc@%d: No available events	Cannot process event.	Refer to application expert. Increase MAXEVENTS in SLEE.cfg.	ACS
111009	CRITICAL	SLEE[%d]: slee_acs(%d) CRITICAL SleeException=%d sleeError.cc@%d:%z	Exception raised from SLEE.	Contact support.	ACS
111010	CRITICAL	SLEE[%d]: slee_acs(%d) CRITICAL SleeInterfaceInstance::new()=%d sleeInterfaceInstance.cc@%d: No available interfaces	Cannot create SLEE interface.	Refer to application expert. Increase MAXINTERFACES in SLEE.cfg.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
111011	CRITICAL	SLEE[%d]: slee_acs(%d) CRITICAL SleeService::new() sleeService.cc@%d: No available services	Cannot start new slee service.	Refer to application expert. Increase MAXSERVICES in SLEE.cfg.	ACS
111012	CRITICAL	SLEE[%d]: slee_acs(%d) CRITICAL: Error attempting to create shared memory key fileZZZ	Cannot create reference file.	Contact support.	ACS
111013	CRITICAL	SLEE[%d]: slee_acs(%d) CRITICAL: sleeStartup: Cannot read configuration file	Cannot read configuration file SLEE.cfg.	Refer to application expert. Check files exist specified in the slee.sh startup file.	ACS
111014	CRITICAL	SLEE[%d]: slee_acs(%d) CRITICAL: sleeStartup: Cannot read file %s %d	Cannot read specified file.	Verify file exists. Check permissions, etc.	ACS
111015	ERROR	SLEE[%d]: slee_acs(%d) ERROR readCurrentCallId=%d sleeRoot.cc@%d:%z	Exception raised from SLEE.	Contact support.	ACS
111016	CRITICAL	SLEE[%d]: slee_acs(%d) ERROR SleeManagementEvent::new()=%d sleeManagementEvent.cc@%d: No available events	Cannot process event.	Refer to application expert. Increase MAXEVENTS in SLEE.cfg.	ACS
111017	ERROR	SLEE[%d]: slee_acs(%d) ERROR: %s %d: Invalid attempt at call processing	Internal error.	Contact support.	ACS
111018	ERROR	SLEE[%d]: slee_acs(%d) ERROR: acsChassisMain: Call ID %d processCall on INAP component op/err ID %d failed	Communications failure.	Contact support.	ACS
111019	ERROR	SLEE[%d]: slee_acs(%d) ERROR: acsChassisMain: Call ID %d TcapPrimitive contains no components	Internal error.	Contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
111020	ERROR	SLEE[%d]: slee_acs(%d) ERROR: acsChassisMain: Unhandled INAP Component (type %d, opErrId %d, call %d)	Internal error.	Contact support.	ACS
111021	ERROR	SLEE[%d]: slee_acs(%d) ERROR: acsEngineRegisterFNType: fast_key %z not found in DB	Reference to a fast key does not exist.	Refer to application expert. Verify fast_key assignments in ACS_FN_TYPE table.	ACS
111022	ERROR	SLEE[%d]: slee_acs(%d) ERROR: DoCCRecharge macro node: Config file error. Reason: cmn::cfg::Value::NotFound: Key not found:%z	Internal error.	Contact support.	ACS
111023	ERROR	SLEE[%d]: slee_acs(%d) ERROR: EngineError: %z , line %d:ppdNode.cc	Error running feature node.	Contact support.	ACS
111024	ERROR	SLEE[%d]: slee_acs(%d) ERROR: Fatal Engine Error (CallID %d, SK %d, CalledPty %s %d, ControlPlan %z	Fatal error with control plan.	Contact support.	ACS
111025	ERROR	SLEE[%d]: slee_acs(%d) ERROR: Invalid FFDiscountRule (%s %d) found in config file, using %s %d rule	Configuration error.	Fix the F&F discount rules.	ACS
111026	ERROR	SLEE[%d]: slee_acs(%d) ERROR: Invalid FFDiscountRule (UNKNOWN) found in config file, using NORMAL rule	Invalid rules found. These will not be used.	Refer to application expert. Correct F&F discount rules.	ACS
111027	ERROR	SLEE[%d]: slee_acs(%d) ERROR: macroNodeProcessor: Unknown fast key %s %d (%s %d)	Feature node has an unmatched fast key assigned.	Refer to application expert. Check table ACS_FN_TYPE.	ACS
111028	ERROR	SLEE[%d]: slee_acs(%d) ERROR: Moving CDR file %s %d to %s %d Failed (error code %d): %s %d: %z	File error.	Refer to application expert. Check full alarm text for details.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
111029	ERROR	SLEE[%d]: slee_acs(%d) ERROR: Node data pointer is NULL	Internal error.	No resolution.	ACS
111030	ERROR	SLEE[%d]: slee_acs(%d) ERROR: ORA123: no data found	Attempt to run a control plan with that does not exist.	Refer to application/Oracle expert. This inconsistency should not exist.	ACS
111031	ERROR	SLEE[%d]: slee_acs(%d) ERROR: ORACLE error--	Oracle internal error.	Contact support.	ACS
111032	ERROR	SLEE[%d]: slee_acs(%d) ERROR: PlayAnnouncement error received, error code =%d	Internal error.	Contact support.	ACS
111033	ERROR	SLEE[%d]: slee_acs(%d) ERROR: shmAttach: Error %d getting INODE for %s %d	Error writing to shared memory.	Contact support.	ACS
111034	ERROR	SLEE[%d]: slee_acs(%d) ERROR: smsTryRecordStats: Memory state not VALID - giving up	Error writing to shared memory.	Contact support.	ACS
111035	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE SleeApplicationAPI=%d sleeApplicationAPI.cc@%d:%z	Exception raised from SLEE.	Contact support.	ACS
111036	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE SleeApplicationInstance::start=% d sleeApplicationInstance.cc@%d:%z	Starting new application.	If raised as CRITICAL then the application failed to start. Refer to application expert.	ACS
111037	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE SleeInterfaceAPI=%d sleeInterfaceAPI.cc@%d:%z	Exception raised from SLEE.	Contact support.	ACS
111038	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE SleeInterfaceInstance::start(=% d sleeInterfaceInstance.cc@%d:%z	Starting new interface.	If raised as CRITICAL then the interface failed to start. Refer to application expert.	ACS
111039	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE SleeRoot::shutdown(=%d sleeRoot.cc@%d: SLEE Shutdown	SLEE is shutting down.	No resolution.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
111040	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE SleeRoot::SleeRoot()=%d sleeRoot.cc@%d: SLEE Startup	SLEE is starting.	No resolution.	ACS
111041	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE: acsCdrFlush: Explicit flush cache (%d bytes).	Information only.	No resolution.	ACS
111042	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE: acsChassisMain: Received APPLICATION_END/APPLICATION_KILL event	Received event and will die.	No resolution.	ACS
111043	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE: acsChassisServiceSetup: Configuring %d service entries	Information only.	No resolution.	ACS
111044	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE: acsChassisServiceSetup: Ignoring incompatible ServiceEntry line	The line referenced in the config file is wrong.	Refer to application expert. Correct line specified in alarm.	ACS
111045	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE: acsChassisServiceSetup: Offending line wasZZZ	Error in acs.conf file.	Refer to application expert. Correct line specified in alarm.	ACS
111046	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE: acsChassisSetup: CDR Max %s %d set to %s %d	Information only.	No resolution.	ACS
111047	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE: acsChassisSetup: CDR to file %s %d format %d	Information only.	No resolution.	ACS
111048	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE: acsChassisSetup: Log PIN is set (lpn field will be written to CDR file).	Information only.	No resolution.	ACS
111049	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE: acsChassisSetupCDR: CDR Field Mask = [%s %d] (final)	Information only.	No resolution.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
111050	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE: acsChassisSetupEmergencyNumbers : Adding ***%d*** to emergency number list	Information only.	No resolution.	ACS
111051	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE: acsChassisSetupEmergencyNumbers : Done with acsChassisSetupEmergencyNumbers	Information only.	No resolution.	ACS
111052	ERROR	SLEE[%d]: slee_acs(%d) NOTICE: acsChassisSetupEmergencyNumbersZ ZZ	Information only.	No resolution.	ACS
111053	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE: acsChassisSetupPinLog: Max %s %d set to %d %s %d	Information only.	No resolution.	ACS
111054	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE: acsChassisSetupPinLog: Pin Log %s %d	Information only.	No resolution.	ACS
111055	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE: acsChassisSetupPinLog: pinLogFail set to %s %d	Information only.	No resolution.	ACS
111056	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE: acsChassisSetupPinLog: pinLogSuccess set to %s %d	Information only.	No resolution.	ACS
111057	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE: acsParseServiceLine: Routing service %s %d to library %s %d	Information only.	No resolution.	ACS
111058	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE: ccsActions : Recieved %d instances of exception message Code(PLUG) TextZZZ	Internal error.	Contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
111059	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE: ccsActions : Recieved %d instances of exception message Code(XSER) TextZZZ	Internal error.	Contact support.	ACS
111060	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE: ccsActions : virtual acsChassisResponse ccs::ccsActionsCREventHandler::h andleResponse(be::Protocol::Mess age*, acsChassisEventParms&) - Recieved an exception message Code(PLUG) TextZZZ	Internal error.	Contact support.	ACS
111061	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE: ccsActions : virtual acsChassisResponse ccs::ccsActionsIREventHandler::h andleResponse(be::Protocol::Mess age*, acsChassisEventParms&) - Recieved an exception message Code(XSER) TextZZZ	Internal error.	Contact support.	ACS
111062	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE: ccsActions : virtual acsChassisResponse ccs::ccsActionsWIEventHandler::h andleResponse(be::Protocol::Mess age*, acsChassisEventParms&) - Recieved an exception message Code(XSER) TextZZZ	Internal error.	Contact support.	ACS
111063	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE: pinLogInitialise: entry	Information only.	No resolution.	ACS
111064	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE: smsRecordStats: Statistic not foundZZZ	Error writing specific stat to shared memory.	Refer to application expert. Check stat exists in SMF_STATISTICS_DEFN table or in statistics.bin depending on your configuration.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
111065	NOTICE	SLEE[%d]: slee_acs(%d) NOTICE: syslog messages will be logged for incoming %s %d	Information only.	No resolution.	ACS
111066	WARNING	SLEE[%d]: slee_acs(%d) WARNING mnpPortNumberNode=%d mnpPortNumberNode.cc@%d: Unknown Carrier. ID: %d	Unknown carrier ID found.	Refer to application expert. Check table MNP_CARRIER.	ACS
111067	WARNING	SLEE[%d]: slee_acs(%d) WARNING: acsChassisServiceFind: No Service for NAME=%s %d	Internal error.	Contact support.	ACS
111068	WARNING	SLEE[%d]: slee_acs(%d) WARNING: handleINAPComponent: TCAP_U_ERROR %d return for invoke %d, sent operation ID %d	Internal error.	Contact support.	ACS
111070	WARNING	SLEE[%d]: slee_acs(%d) WARNING: No Msid Rules configured for %s %d	No Msid rules found.	Refer to application expert. Specify rules.	ACS
111072	NOTICE	acsStatsLocalSLEE: acsStatsLocalSLEE(%d) NOTICE SleeInterfaceAPI=%d sleeInterfaceAPI.cc@%d: Dialog timeout index (%d) exceeds maximum (%d)	Information only.	No resolution.	ACS
111073	ERROR	SLEE[%d]: slee_acs(%d) ERROR: acsChassisServiceSetup: Unable to open configuration file No such file or directory	specified config file is missing/corrupt.	Assuming basic UNIX skills (Check the following). 1) Check validity and permissions of the config file specified in the alarm.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
111074	NOTICE	slee_acs: slee_acs(%d) NOTICE: ccsActions : Recieved %d instances of exception message Code(VWAR) Text(Processing Exception: VWARS: be VWARS RuntimeError: Error running plug-in %s %d: CCS RuntimeError: AccountRefZZZ	Received exception from the BE.	Contact support.	ACS
111075	NOTICE	slee_acs: slee_acs(%d) NOTICE: ccsActions : Recieved %d instances of exception message Code(WALT) Text(Data Exception: Bad value (???) for field WALT: Bad value for field WALT (%d))	Received exception from the BE.	No resolution.	ACS
111076	NOTICE	slee_acs: slee_acs(%d) NOTICE: ccsActions : virtual acsChassisResponse ccs::ccsActionsIREventHandler::h andleResponse(be::Protocol::Mess age*, acsChassisEventParms&) - Recieved an exception message Code(VWAR) TextZZZ	Received exception from the BE.	Contact support.	ACS
111077	NOTICE	slee_acs: slee_acs(%d) NOTICE: ccsActions : virtual acsChassisResponse ccs::ccsActionsVRWEventHandler:: handleResponse(be::Protocol::Mes sage*, acsChassisEventParms&) - Recieved an exception message Code(XSER) TextZZZ	Received exception from the BE.	Contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
111078	NOTICE	slee_acs: slee_acs(%d) NOTICE: ccsActions : virtual acsChassisResponse ccs::ccsActionsWIEEventHandler::h andleResponse (be::Protocol::Mess age*, acsChassisEventParms&) - Recieved an exception message Code (PLUG) TextZZZ	Received exception from the BE.	Contact support.	ACS
111079	NOTICE	slee_acs: slee_acs(%d) NOTICE: ccsActions : virtual acsChassisResponse ccs::ccsActionsWIEEventHandler::h andleResponse (be::Protocol::Mess age*, acsChassisEventParms&) - Recieved an exception message Code (WALT) TextZZZ	Received exception from the BE.	Contact support.	ACS
111080	ERROR	slee_acs: slee_acs(%d) ERROR: Call ID %d non-BEGIN Primitive Type %d received with null context	Message received with a null ACS Chassis context.	Contact support.	ACS
111081	ERROR	slee_acs: slee_acs(%d) ERROR: EngineError: Invalid Attempt at Call Processing, line %d:SelectLanguage.cc	Call processing not allowed for this call.	Contact support.	ACS
111082	ERROR	slee_acs: slee_acs(%d) ERROR: acsSLEEChassis_t::armAndConnect : Zero-length normalised DRA in call to %d:%z	Empty destination routing address.	Contact support.	ACS
111083	ERROR	slee_acs: slee_acs(%d) ERROR: handleINAPComponent: TCAP_U_ERROR %d returned for invoke %d, unhandled sent operation ID %d	Internal error.	No action required.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
111084	NOTICE	slee_acs: slee_acs(%d) NOTICE: Too many requests waiting for the BE client. Number in queue = %d Max Allowed %d.	Throttling enabled.	No action required.	ACS
111085	NOTICE	slee_acs: slee_acs(%d) NOTICE: ccsActions : Recieved %d instances of exception message Code(%s %d) Text(Processing Exception: VWARS:%z	Received a processing exception from the BE.	Refer to application expert. Reference extra text in the alarm string.	ACS
111086	NOTICE	slee_acs: slee_acs(%d) NOTICE: ccsActions : Recieved %d instances of exception message Code(%s %d) Text(Communications Exception:%z	Received a communications exception from the BE.	Refer to application expert. Reference extra text in the alarm string.	ACS
111087	NOTICE	slee_acs: slee_acs(%d) NOTICE: ccsActions : Recieved %d invalid messages	A report on invalid messages.	No action required.	ACS
111088	NOTICE	slee_acs: slee_acs(%d) NOTICE: ccsActions : virtual acsChassisResponse ccs::%s %d::handleResponse(be::Protocol: :Message*, acsChassisEventParms&) - Recieved an exception message Code(%s %d) Text(Communications Exception:%z	Received a communications exception from the BE.	Refer to application expert. Reference extra text in the alarm string.	ACS
111089	NOTICE	slee_acs: slee_acs(%d) NOTICE: ccsActions : virtual acsChassisResponse ccs::%s %d::handleResponse(be::Protocol: :Message*, acsChassisEventParms&) - Recieved an exception message Code(%s %d) Text(Processing Exception:%z	Received a processing exception from the BE.	Refer to application expert. Reference extra text in the alarm string.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
111090	NOTICE	slee_acs: slee_acs(%d) NOTICE: ccsActions : virtual acsChassisResponse ccs::%s %d::handleResponse(be::Protocol: :Message*, acsChassisEventParms&) - Recieved an invalid message	Received a general exception from the BE.	Contact support if alarm persists.	ACS
111091	CRITICAL	slee_acs: slee_acs(%d) CRITICAL: ReloadLowThresholdActionHandler: :doAction() could not send BB the RLT request.	Inter-process communications error.	Contact support	ACS
111092	ERROR	slee_acs: slee_acs(%d) ERROR getAccountInformation=%d ccsSvcLibraryUtil.cc@%d: MUP ABS LoadService: Unable to map call plan name!	Control plan name not defined in data set	Refer to application expert. Check database for existence of control plan name	ACS
111093	NOTICE	slee_acs: slee_acs(%d) NOTICE: ccsActions : Recieved %d instances of exception message Code(%z) Text(Data Exception: Bad value (%d) for field %z)	Received exception from the BE.	Contact support	ACS
111094	NOTICE	slee_acs: slee_acs(%d) NOTICE: ccsActions : virtual acsChassisResponse ccs::ccsActionsCREventHandler::h andleResponse(be::Protocol::Mess age*, acsChassisEventParms&) - Recieved an exception message Code(%z) Text(Data Exception: Bad value (%d)%z	Received exception from the BE.	Contact support	ACS
111095	WARNING	slee_acs: slee_acs(%d) WARNING: storeInvokeIds: unknown dialog: %d	SLEE has deleted dialog	Contact support	ACS

Alarm	Severity	Text	Cause	Resolution	Service
111096	NOTICE	slee_acs: slee_acs(%d) NOTICE: ccsActions : virtual acsChassisResponse ccs::ccsActionsINEREventHandler: :handleResponse (be::Protocol::Me ssage*, acsChassisEventParms&) - Recieved an exception message Code(%z) Text(Data Exception: Bad value (%d)%z	Received exception from the BE.	Contact support	ACS
111097	ERROR	slee_acs: slee_acs(%d) ERROR: acsCallInitiationAction::classIn it: Failed registration of acsCallInitiationAction chassis action	acsCallInitiation chassis action failed to register with the ACS Chassis successfully.	Contact support.	ACS
111098	WARNING	slee_acs: slee_acs(%d) ERROR: acsCallInitiationAction::classIn it: Bad value %d for CallInitiationTimeoutToleranceSe conds in /IN/service_packages/ACS/etc/acs .conf section %s must be between 0 and 65535, using 65535	CallInitiationTimeou tToleranceSeconds parameter configured incorrectly	Refer to application expert and reconfigure parameter	ACS
111100	ERROR	slee_acs: slee_acs(%d) ERROR: acsCallInitiationAction::classIn it: Can not get SLEE Application API	Call Initiation action is unable to communicate with the SLEE	Restart the SLEE and contact support if problem reoccurs	ACS
111101	ERROR	slee_acs: slee_acs(%d) ERROR: acsCallInitiationAction::classIn it: Can not get handle to CallInitiationActionDefaultTcapI nterface SLEE Interface %s %d	Call Initiation action is unable to communicate with the TCAP interface	Ensure that the TCAP interface is configured to a valid slee interface that is currently running. Restart the SLEE.	ACS
111102	ERROR	slee_acs: slee_acs(%d) ERROR: Could not denormalise number %d, missing DenormalisationRule in %s %d, %s %d section	The denormalisation rules are not correctly configured	Refer to application expert and configure denormalisation rules	ACS

Alarm	Severity	Text	Cause	Resolution	Service
111103	ERROR	slee_acs: slee_acs(%d) ERROR: Unexpected event report BCSM types received	An event report BCSM message was received unexpectedly	Contact support	ACS
111104	ERROR	slee_acs: slee_acs(%d) ERROR: Timed out: TCAP notice received	The call initiation timed out	Check network status	ACS
111105	ERROR	slee_acs: slee_acs(%d) ERROR: TCAP Continue (%z) or TCAP End (%z) expected not the received %z	An unexpected TCAP message was received	Contact support	ACS
111106	ERROR	slee_acs: slee_acs(%d) ERROR: INAP (%z), not (%z) expected	An unexpected INAP message was received	Contact support	ACS
111111	ERROR	slee_acs: slee_acs(%d) ERROR: Could not denormalise number %d, missing DenormalisationRule in acs.conf	The denormalisation rules are not correctly configured	Refer to application expert and configure denormalisation rules	ACS
111112	CRITICAL	slee_acs: slee_acs(%d) CRITICAL: acsTcapHandoverAction::Initialise: Failed registration of acsTcapHandoverAction chassis action	Tcap Handover chassis action failed to register with the ACS Chassis successfully.	Contact support.	ACS
111113	CRITICAL	slee_acs: slee_acs(%d) CRITICAL: acsTcapHandoverAction::Initialise: No SLEE API	Tcap Handover action is unable to communicate with the SLEE	Restart the SLEE and contact support if problem reoccurs	ACS
111115	CRITICAL	slee_acs: slee_acs(%d) CRITICAL: acsTcapHandoverAction::Initialise: Loading of network entities failed	The network entities could not be retrieved from the configuration file	Refer to application expert and configure network entities	ACS
111116	CRITICAL	slee_acs: slee_acs(%d) CRITICAL: acsTcapHandoverAction::doAction: Unable to get invoke ID	The invoke ID received by the chassis action was invalid	Contact support	ACS

Alarm	Severity	Text	Cause	Resolution	Service
111117	ERROR	slee_acs: slee_acs(%d) ERROR: acsTcapHandoverAction::doAction: No network entity supplied	No network entity was supplied to the chassis action	Contact support	ACS
111118	CRITICAL	slee_acs: slee_acs(%d) CRITICAL: acsTcapHandoverAction::doAction: SLEE Exception sending TCAP_BEGIN	The Tcap Handover action was unable to send the TCAP BEGIN message	Check that all SLEE processes are running, contact support if the issue persists	ACS
111119	CRITICAL	slee_acs: slee_acs(%d) CRITICAL: acsTcapHandoverAction::doAction: Failed to send TCAP_BEGIN	The Tcap Handover action was unable to send the TCAP BEGIN message	Check network status, contact support if the issue persists	ACS
111120	ERROR	slee_acs: slee_acs(%d) ERROR: ATPD invalid action type (%d), response type (%d) in acs::ATPDCallInProgress	The ATPD node received an invalid response from slee_acs	Contact support	ACS
111121	ERROR	slee_acs: slee_acs(%d) ERROR: ATPD invalid action type (%d), response type (%d) in acs::ATPDWaitForCallData	The ATPD node received an invalid response from slee_acs	Contact support	ACS
111122	ERROR	slee_acs: slee_acs(%d) ERROR: acsCIN node: Could not obtain NodePtr	The Call Initiation node could not read data from the control plan	Check the control plan is correctly compiled. Check the control plan was replicated successfully.	ACS
111123	ERROR	slee_acs: slee_acs(%d) ERROR: acsCIN node: No ICA Destination Routing Address	The Call Initiation node could not read the ICA destination routing address from the control plan	Check the control plan is correctly compiled. Check the control plan was replicated successfully.	ACS
111124	ERROR	slee_acs: slee_acs(%d) ERROR: acsCIN node: no answer timeout (%d) is outside the valid range (1..65535)	The Call Initiation node retrieved an invalid no answer timeout from the control plan	Check configured values in the control plan.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
111125	ERROR	slee_acs: slee_acs(%d) ERROR: acsCIN node: serviceKey (%d) is greather than 31 bits, must be 0 to 2147483647	The Call Initiation node retrieved an invalid service key from the control plan	Check configured values in the control plan.	ACS
111126	ERROR	slee_acs: slee_acs(%d) ERROR: NumberNormalise: wrong response type	The number normalisation node received an invalid response from slee_acs	Contact support	ACS
111127	WARNING	slee_acs: slee_acs(%d) WARNING: CDR Free-format area exceeded, Setting service specific CDR information to NULL	The text in the set CDR node is too long	Shorten the configured text in set CDR nodes in the control plan	ACS
111128	ERROR	slee_acs: slee_acs(%d) ERROR: Error parsing %s %d line %s %d in %s /%s section %s : %s	The specified line in the configuration file is invalid	Correct the error in the configuration file	ACS
111129	ERROR	slee_acs: slee_acs(%d) ERROR: Could not normalise NOA %d, %s , missing NormalisationRule in acs.conf, acsChassis section	Normalisation rules for the specified NOA are not present in the configuration file	Refer to an application expert and configure the normalisation rules	ACS
111130	ERROR	slee_acs: slee_acs(%d) ERROR: acsChassisActions: acs::ATPDChassisAction Init Failed!	The chassis action cannot be initialised	Ensure that the shared library paths are set to include the libacsChassisActions.so file	ACS
111131	ERROR	slee_acs: slee_acs(%d) ERROR: acsChassisActions: acs::ATPDGetCIRDataChassisAction Init Failed!	The chassis action cannot be initialised	Ensure that the shared library paths are set to include the libacsChassisActions.so file	ACS
111132	ERROR	slee_acs: slee_acs(%d) ERROR: acsChassisActions: acs::acsTcapHandover Init Failed!	The chassis action cannot be initialised	Ensure that the shared library paths are set to include the libacsChassisActions.so file	ACS

Alarm	Severity	Text	Cause	Resolution	Service
111133	ERROR	slee_acs: slee_acs(%d) ERROR: acsChassisActions: acs::CallInitialisation Init Failed!	The chassis action cannot be initialised	Ensure that the shared library paths are set to include the libacsChassisActions.so file	ACS
111135	ERROR	slee_acs: slee_acs(%d) ERROR: acsChassisGetPluginContextBlockS ize: Unknown pluggable-action- type %d, service-domain %d	The action type is not recognised	Contact support	ACS
111137	WARNING	slee_acs: slee_acs(%d) WARNING: FCI length %d has been truncated to %d	The FCI information was truncated	Contact support	ACS
111138	ERROR	slee_acs: slee_acs(%d) ERROR: acsChassisRegisterEventHandler: Attempted to register more than %d on a single call!	Too many event handlers are currently in use for a call	Contact support	ACS
111139	ERROR	slee_acs: slee_acs(%d) ERROR: acsChassisReplicationUpdateProfi le: Cannot get Replication Event	Unable to create a replication event	Restart the SLEE. If the issue persists then contact support.	ACS
111140	ERROR	slee_acs: slee_acs(%d) ERROR: acsChassisInvokePluggableAction: Unable to find pluggable-action- type %d, in any relevant domain	The plugable action type was not recognised in any service domains	Contact Support	ACS
111141	ERROR	slee_acs: slee_acs(%d) ERROR: getHandlerOfActionType: Unknown pluggable-action-type %d, domain %d	The pluggable action was not recognised in the specified domain	Contact Support	ACS
111142	ERROR	slee_acs: slee_acs(%d) ERROR: getHandlerOfActionType: Unknown service domain for pluggable- action-type %d, domain %d	The service domain was not associated with the pluggable action type	Contact Support	ACS
111143	ERROR	slee_acs: slee_acs(%d) ERROR: acsChassisInvokePluggableAction: Unknown pluggable-action-type %d	The pluggable action type was not recognised	Contact Support	ACS

Alarm	Severity	Text	Cause	Resolution	Service
111144	CRITICAL	slee_acs: slee_acs(%d) CRITICAL: acsTcapHandoverAction::doAction: TCAP Dialog unavailable	The Tcap Handover action could not retrieve a dialog to the SLEE	Check the number of free dialogs in the system. Check for resource leaks. Restart the SLEE and contact support if the issue reoccurs	ACS
111145	ERROR	slee_acs: slee_acs(%d) ERROR: acsTcapHandoverAction::doAction: No originating address available.	The originating address could not be retrieved from the TCAP begin received by the TCAP Handover action	Contact support	ACS
111146	ERROR	slee_acs: slee_acs(%d) ERROR: MTCH2: No number list found in profile %d, with tag 0x%s %d for Call ID %d	The specified tag in the specified profile does not contain a number matching list.	Consult the ACS user guide. Populate a number list at the specified tag or specify the correct profile and tag.	ACS
111147	ERROR	slee_acs: slee_acs(%d) ERROR: SCC2: Invalid action status, action type = %d, response type = %d	An unknown event occurred while trying to retrieve profile data	Refer to application expert. This inconsistency should not exist.	ACS
111148	ERROR	slee_acs: slee_acs(%d) ERROR: SCC2: Carrier code not found at profile block %d, with tag hex 0x%s %d for Call ID %d	The specified tag in the specified profile does not contain a carrier code.	Consult the ACS user guide. Populate a carrier code at the specified tag or specify the correct profile and tag.	ACS
111149	ERROR	slee_acs: slee_acs(%d) ERROR: SCC2: Carrier code at profile block %d, with tag hex 0x%s %d has length %d > maximum allowed %d. Call ID is %d	The carrier code specified in the profile is too long.	Specify a shorter carrier code.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
111150	CRITICAL	slee_acs: slee_acs(%d) CRITICAL: Could not find IDP action handler	The library libacsChassisActions .so was not successfully loaded or is out of date.	Check that the library path of acs_oper includes /IN/service_packages/ACS/lib and that libacsChassisActions.so exists in this directory and nowhere else. Check that ChassisPlugin libacsChassisActions.so is specified in the acsChassis section of acs.conf. Check that libacsChassisActions.so is the one shipped with ACS 2.4.0.21 or patch 25499 or later. Check the system log for errors loading libacsChassisActions.so.	ACS
111151	ERROR	slee_acs: slee_acs(%d) ERROR: Could not Set Chassis Calling Party Number	Internal consistency error.	Contact support.	ACS
111152	ERROR	slee_acs: slee_acs(%d) ERROR: Invalid CLI Presentation Indicator	The presentation restricted indicator from the InitialDP CallingPartyNumber does not have an allowed value (0,1 or 2).	Use a protocol analyzer or other tracing tool to identify the contents and source of the IDPs causing this problem. Fix the network element which sends the IDPs.	ACS
111153	ERROR	slee_acs(%d) ERROR: acsMacroBranchOnProtocol: Internal error unknown switch type %d	Internal consistency error.	Contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
111154	ERROR	slee_acs: slee_acs(%d) ERROR: Attempt to set CLI Presentation Indicator to invalid value: %d	A control plan was run with a Set CLI Presentation Bit node which attempts to set the Calling Party Number presentation restricted indicator to an invalid value i.e. a value other than 0,1 or 2.	Edit the control plan and set the Presentation Bit field of the offending node to a valid value. Save the control plan.	ACS
111155	ERROR	slee_acs: slee_acs(%d) ERROR: Could not retrieve Chassis Calling Party Number	Internal consistency error.	Contact support.	ACS
111157	ERROR	slee_acs: slee_acs(%d) ERROR: Set Buffer Node, manipulation of Location area code unsupported - exiting	A control plan was run with a Set Buffer node which attempts to set the Location Area Code buffer.	Edit the control plan and set the To Number Buffer field of the offending node to a valid value. Save the control plan.	ACS
111158	ERROR	slee_acs: slee_acs(%d) ERROR: Set Buffer Node, manipulation of Cell Identity unsupported - exiting	A control plan was run with a Set Buffer node which attempts to set the Cell Identity buffer.	Edit the control plan and set the To Number Buffer field of the offending node to a valid value. Save the control plan.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
111159	ERROR	slee_acs: slee_acs(%d) ERROR: Set Buffer Node, from buffer is not a valid number :%s %d	A control plan was run with a Set Buffer node for which the From Number Buffer or the specified profile location contains a string with characters other than 0-9,A-F,* and #.	Correct the control plan and/or the profile data.	ACS
111160	ERROR	slee_acs: slee_acs(%d) ERROR: Set Buffer Node, Buffer would be too long, length %d > maximum allowed %d.	A control plan was run with a Set Buffer node which results in a digit string too long to fit in the From Number Buffer.	Correct the control plan and/or the profile data.	ACS
111161	ERROR	slee_acs: slee_acs(%d) ERROR: Set Buffer Node, From buffer at profile block %d, with tag hex 0x%s %d has length %d > maximum allowed %d.	A control plan was run with a Set Buffer node which attempts to read a number from the the specified profile location which is too long.	Provision a shorter number in the profile.	ACS
111162	ERROR	slee_acs: slee_acs(%d) ERROR: Wait For Disconnect setup failed because disconnect not armed, call ID = %d	A wait for disconnect node has been used at a point in the control plan where disconnect is not armed.	Correct the control plan	ACS
111163	ERROR	slee_acs: slee_acs(%d) ERROR: Cannot arm busy as interrupted and notify and continue simulataneously, call ID = %d.	Internal consistency error.	Contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
111164	ERROR	slee_acs: slee_acs(%d) ERROR: Cannot arm no answer as interrupted and notify and continue simulataneously, call ID = %d.	Internal consistency error.	Contact support.	ACS
111165	ERROR	slee_acs: slee_acs(%d) ERROR: Cannot arm RSF as interrupted and notify and continue simulataneously, call ID = %d.	Internal consistency error.	Contact support.	ACS
111166	ERROR	slee_acs: slee_acs(%d) ERROR: Only one monitor mode for disconnect on leg 1 may be specified, call ID = %d.	Internal consistency error.	Contact support.	ACS
111167	ERROR	slee_acs: slee_acs(%d) ERROR: Only one monitor mode for disconnect on leg 2 may be specified, call ID = %d.	Internal consistency error.	Contact support.	ACS
111168	WARNING	slee_acs: slee_acs(%d) WARNING: acsChassisSetup: Value for maxAnnouncementTextBytes is too great (%d), setting to the maximum of %d	Internal consistency error.	Specify a lower value for maxAnnouncementTextBytes in acs.conf	ACS
111169	ERROR	slee_acs: slee_acs(%d) ERROR: buildPlayAnnouncement: length of text %d is outside the allowed range 1 to %d	Internal consistency error.	Increase the size of the maxAnnouncementTextBytes in acs.conf or decrease the length of text being sent.	ACS
111170	ERROR	slee_acs: slee_acs(%d) ERROR: playAnnouncement: length of text %d is outside the allowed range 1 to %d	Internal consistency error.	Increase the size of the maxAnnouncementTextBytes in acs.conf or decrease the length of text being sent.	ACS
111171	ERROR	slee_acs: slee_acs(%d) ERROR: collectDigits: length of text %d is outside the allowed range 1 to %d	Internal consistency error.	Increase the size of the maxAnnouncementTextBytes in acs.conf or decrease the length of text being sent.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
111172	WARNING	%z acsEngine: convertStringToPrefixTree: Unable to add %s %d into prefix tree.	Internal software error. The number provided is not a valid prefix tree entry.	Correct the input data and try again. Contact support. No further information can be obtained.	ACS
111173	ERROR	%z getDomainedEventHandlerOfActionT ype: Unknown pluggable-action- type: %d, domain: u	Internal software error.	Contact support. No further information can be obtained.	ACS
111174	ERROR	%z getDomainedEventHandlerOfActionT ype: Unknown service domain for pluggable-action-type: %d, domain: u	Internal software error.	Contact support. No further information can be obtained.	ACS
111175	ERROR	%z getDomainedActionInitiatedEventH andlerOfActionType: Unknown pluggable-action-type: %d, domain: u	Internal software error.	Contact support. No further information can be obtained.	ACS
111176	ERROR	%z getDomainedActionInitiatedEventH andlerOfActionType: Unknown service domain for pluggable- action-type: %d, domain: u	Internal software error.	Contact support. No further information can be obtained.	ACS
111177	WARNING	%z acsCreatePrefixTree: convertStringToPrefixTree: Unable to add %s %d into prefix tree. Did not pass limits check	The number has been restricted by the prefix tree limitations.	Check the input data and limitations for valid numbers. Contact support. No further information can be obtained.	ACS
111178	WARNING	%z acsCreatePrefixTree: convertStringToPrefixTree: Unable to add %s %d into prefix tree. Tree full.	The number has been restricted by the prefix tree limitations.	Check the input data and limitations for valid numbers. Contact support. No further information can be obtained.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
111179	WARNING	%z acsCreatePrefixTree: convertStringToPrefixTree: Unable to add %s %d into prefix tree.	The number has been restricted by the prefix tree limitations.	Check the input data and limitations for valid numbers. Contact support. No further information can be obtained.	ACS
111180	ERROR	%z %s %d() : Failed to retrieve nodePtr, disconnecting call.	Internal software error.	Contact support. No further information can be obtained.	ACS
111181	ERROR	%z %s %d() : Prefix Tree Profile does not exist. No entry to extract.	An invalid prefix tree entry position was specified.	Check control plan configuration. Contact support. No further information can be obtained.	ACS
111182	ERROR	%z %s %d() : Entry Profile does not exist. No entry to extract.	An invalid prefix tree entry position was specified.	Check control plan configuration. Contact support. No further information can be obtained.	ACS
111183	ERROR	%z %s %d() : Prefix tree empty. No entry to extract.	An invalid prefix tree entry position was specified.	Check control plan configuration. Contact support. No further information can be obtained.	ACS
111184	ERROR	%z %s %d() : %s %d	Internal software error.	Contact support. No further information can be obtained.	ACS
111185	ERROR	%z %s %d() : Invalid position specified for prefix tree with size <%d>	An invalid prefix tree entry position was specified, outside of the specified maximum number of entries.	Check control plan configuration. Contact support. No further information can be obtained.	ACS
111186	ERROR	%z %s %d() : Profile Data Not Updated	The profile block was read-only and an attempt was made to update it. Internal software error.	Contact support. No further information can be obtained.	ACS
111187	ERROR	%z %s %d() : Invalid Action Status	Internal software error.	Contact support. No further information can be obtained.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
111188	ERROR	%z %s %d() : Too many instances of the Loop Limit feature node traversed (maximum 12).	There can be a maximum of 12 loop limit nodes in a control plan.	Check control plan configuration. Contact support. No further information can be obtained.	ACS
111189	ERROR	%z %s %d() : Attempt to break Limit value specified in a Loop Limit FN instance.	Internal software error.	Contact support. No further information can be obtained.	ACS
111190	ERROR	DEF123slee_acs: slee_acs(%d) ERROR: acsChassisActions: HierarchicalProfileStore Init Failed!	The HierarchicalProfileStore chassis action failed to start.	There will be additional errors in the syslog detailing the reason for the failure. Resolve them and restart ACS.	ACS
111191	ERROR	DEF123slee_acs: slee_acs(%d) ERROR: acsChassisActions: HierarchicalProfileRetrieve Init Failed!	The HierarchicalProfileRetrieve chassis action failed to start.	There will be additional errors detailing the actual cause for the failure. Resolve those errors and restart ACS.	ACS
111192	CRITICAL	DEF123slee_acs: slee_acs(%d) CRITICAL: acsChassisHierarchicalProfileStoreAction::classInit: Failed registration of	The HierarchicalProfileStore chassis action failed to register with ACS.	Refer to Platform Expert.	ACS
111193	CRITICAL	DEF123slee_acs: slee_acs(%d) CRITICAL: acsChassisHierarchicalProfileRetrieveAction::classInit: Failed registration of	The HierarchicalProfileRetrieve chassis action failed to register with ACS.	Refer to platform expert.	ACS
111194	CRITICAL	DEF123slee_acs: slee_acs(%d) CRITICAL: Could not lookup RetrieveHeirarchicalProfileField chassis action handler	The chassis action failed to initialise.	Make sure that the ACS pluggable chassis action library is properly configured and restart ACS.	ACS
111195	CRITICAL	DEF123slee_acs: slee_acs(%d) CRITICAL: Could not lookup StoreHeirarchicalProfileField chassis action handler	The chassis action failed to initialise.	Ensure that the ACS pluggable chassis action library is properly configured and restart ACS.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
111200	WARNING	slee_acs: slee_acs(%d) WARNING: ActionsAPI backwards compatibility mode enabled, this may impact performance - please upgrade component providing actions library %s %d	Upgrade needed	Upgrade the package providing the library.	ACS
111201	ERROR	slee_acs: slee_acs(%d) ERROR: acsCallInitiationAction::classInit: Bad value %d for CallInitiationCallingPartysCategoryExt in /IN/service_packages/ACS/etc/acs.conf section %s must be between 0 and 255	CallInitiationCallingPartysCategoryExt parameter configured incorrectly	Refer to application expert and reconfigure parameter	ACS
111202	ERROR	slee_acs: slee_acs(%d) ERROR: acsEngineRegisterFNType: No macro node description found for fast_key %z ignored	Macro node missing from ACS database	Refer to application expert and reconfigure parameter	ACS
111203	ERROR	slee_acs: slee_acs(%d) WARNING: NOA Rules not found in file. %z	Normalisation rules arent correct.	The error message details the actual cause for the normalisation rule read failure. Resolve that and restart ACS.	ACS
111204	ERROR	slee_acs: slee_acs(%d) WARNING: No normalisation rules found in file. %z	Normalisation rules werent found in the file	This may be of informational purposes only. Correct if you want normalisation rules.	ACS
111205	ERROR	slee_acs: slee_acs(%d) WARNING: No denormalisation rules found in file. %z	Denormalisation rules werent found in the file	This may be of informational purposes only. Correct if you want denormalisation rules.	ACS
111206	ERROR	slee_acs: slee_acs(%d) NOTICE: Statistics will %z be broken down by service name	Information only.	No resolution	ACS
111207	ERROR	slee_acs: slee_acs(%d) NOTICE: Statistics will %z be broken down by service key	Information only.	No resolution	ACS

Alarm	Severity	Text	Cause	Resolution	Service
111208	ERROR	slee_acs: slee_acs(%d) NOTICE: Statistics will %z be broken down by call plan	Information only.	No resolution	ACS
111209	ERROR	slee_acs: slee_acs(%d) NOTICE: Extra statistics will %z be reported	Information only.	No resolution	ACS
111210	WARNING	DEF123 slee_acs(%d) WARNING: %d timed out calls ended in last 123s. AWOL pending queue size = %d	Either AWOL calls were closed or there are AWOL calls available for closing since the last summary report.	No resolution.	ACS
111211	WARNING	DEF123 slee_acs(%d) WARNING: Ending Call %d. TID L.0xHEX_REPEATED R.0xHEX_REPEATED Sent operation(s) %s %d. Received timeout 123s ago. Service Handle %s %d. Origin Address - %s %d	Closing AWOL call.	No resolution.	ACS
111212	WARNING	DEF123 slee_acs(%d) WARNING: Ending Call %d. TID L.0xHEX_REPEATED R.0xHEX_REPEATED Sent operation(s) %s %d. Received timeout 123s ago. Origin Address - %s %d	Closing AWOL call.	No resolution.	ACS
111213	ERROR	DEF123 slee_acs(%d) ERROR: Call ID %d is AWOL. processCall() failed.	Abort message received but we failed to process the call successfully.	Contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
111214	ERROR	DEF123 slee_acs(%d) ERROR: Failed to get AWOL configuration. No context or global instance.	Unable to access configuration for service instance.	Refer to application expert. Verify that all the necessary parameters exist in the ACS.cfg file found in /IN/service_packages/ACS/etc. If unsure of configuration details then contact support.	ACS
111215	ERROR	DEF123 slee_acs(%d) ERROR: Failed to get AWOL configuration. No %s %d or Global instance.	Unable to access configuration for service instance.	Refer to application expert. Verify that all the necessary parameters exist in the ACS.cfg file found in /IN/service_packages/ACS/etc. If unsure of configuration details then contact support.	ACS
111216	ERROR	acsCompilerDaemon: acsCompilerDaemon(%d) ERROR: compileCallPlans:%z : %z	ORACLE error - processing the ACS control plan compiled list.	Refer to ORACLE/application expert first (Check the following). 1) Verify that ORACLE is running through checking the status of the listener(lsnrctl) and restart ORACLE only if neccessary. 2) Check the environment variables and/or configuration files: ORACLE_SID(environment), tnsnames.ora(configuration file), listener.ora(configuration file). Verify that the username and password for the current machine is correct. 3) Observe startup output for errors. Finally contact support.	ACS
111217	NOTICE	acsProfileCompiler: acsProfileCompiler(%d) NOTICE: Startup	Information only.	No resolution.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
111218	NOTICE	acsProfileCompiler: acsProfileCompiler(%d) NOTICE: Using Config file %z	Information only.	No resolution.	ACS
111219	ERROR	acsProfileCompiler: acsProfileCompiler(%d) ERROR: Error connecting to Oracle. Exiting.	Cannot connect to ORACLE.	Refer to ORACLE/application expert first (Check the following). 1) Verify that ORACLE is running through checking the status of the listener(lsnrctl) and restart ORACLE only if necessary. 2) Check the environment variables and/or configuration files: ORACLE_SID(environment), tnsnames.ora(configuration file), listener.ora(configuration file). 3) Verify that the username and password for the current machine is correct. 4) Observe startup output for errors. Finally contact support.	ACS
111220	CRITICAL	acsStatisticsDBInserter: acsStatisticsDBInserter(%d) CRITICAL: Cannot resolve hostZZZ	Cannot resolve remote host name.	Refer to application expert. Check all nodes are operational and verify connectivity.	ACS
111221	ERROR	DEF123 slee_acs(%d) ERROR: %z : No value found for the parameter (%d), disconnecting call.	Failed to find Open Notification parameter value.	Contact support.	ACS
111222	ERROR	DEF123 slee_acs(%d) ERROR: %z : Unexpected message type received, cant process variable part. Action type (%d), Response type (%d)	Unexpected response to request to retrieve profile fields.	Contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
111223	ERROR	DEF123 slee_acs(%d) ERROR: %z : Unexpected message type received, marking notification as failed. Action type (%d), Response type (%d)	Unexpected response to request to retrieve profile fields.	Contact support.	ACS
111224	ERROR	DEF123 slee_acs(%d) ERROR: %z : Unexpected state %d, stopping notification processor	Received processing request when in an invalid state.	Contact support.	ACS
111225	ERROR	DEF123 slee_acs(%d) ERROR: Internal error: couldnt get notification plugin %z	Plugin called when not valid.	Contact support.	ACS
111226	ERROR	DEF123 slee_acs(%d) ERROR: Variable part ID %d not found, skipping	Unable to find variable part of notification.	Contact support.	ACS
111227	NOTICE	DEF123 slee_acs(%d) NOTICE: acsNotificationProcessor: default fromAddress configured as: %z	Information only.	No resolution.	ACS
111228	WARNING	DEF123 slee_acs(%d) WARNING: acsNotificationProcessor: notificationIF.fromAddress missing or empty	Configuration parameter not specified.	Check the configuration file.	ACS
111229	ERROR	DEF123 slee_acs(%d) ERROR: Internal error: Invalid data type %d	Invalid notification variable part data type.	Contact support.	ACS
111230	ERROR	DEF123 slee_acs(%d) ERROR: Invalid variable part date/time format string %z (should have three elements separated by)	Invalid notification variable part format string.	Contact support.	ACS
111231	ERROR	DEF123 slee_acs(%d) ERROR: Invalid variable part format string %z	Invalid notification variable part format string.	Contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
111232	ERROR	DEF123 slee_acs(%d) ERROR: No send message handler found for transport %d	Message handler not registered.	Contact support.	ACS
111233	WARNING	DEF123 slee_acs(%d) WARNING: Unexpected call flow. Aborting when there is an outstanding Apply Charging request. %z	Call aborted when an Apply Charging request was outstanding.	Check whether there are any billing implications.	ACS
111234	ERROR	acsTriggerIF(%d) Trigger failed: dialog closed by service	Failed to run the triggered control plan before closing dialog.	Check configuration settings and control plans.	ACS
111235	ERROR	acsTriggerIF(%d) Trigger failed: unexpected INAP component	Triggered control plan sent out unexpected INAP message.	Check and correct control plan actions.	ACS
111236	ERROR	acsTriggerIF(%d) Trigger failed: received unexpected INAP result	Triggered control plan sent out unexpected INAP message.	Check and correct control plan actions.	ACS
111237	ERROR	acsTriggerIF(%d) Trigger failed: received INAP error	Triggered control plan sent out unexpected INAP message.	Check and correct control plan actions.	ACS
111238	ERROR	acsTriggerIF(%d) Trigger failed: transaction timed out	Triggered control plan failed to complete within timeout period.	Increase acsTriggerIF.triggerTimeOutSecs value and check control plan actions.	ACS
111239	ERROR	acsTriggerIF(%d) Normalisation rules could not be loaded	The acsTriggerIF.numberRules parameter contents could not be processed.	Check and correct acsTriggerIF.numberRules parameter contents.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
111240	ERROR	acsTriggerIF(%d) Failed to read configuration: %s %d	No acsTriggerIF configuration settings.	Check the configuration file contents, then restart the SLEE.	ACS
111241	ERROR	acsTriggerIF(%d) Received unexpected event of type %s %d	Internal software error.	Contact support. No further information can be obtained.	ACS
111242	WARNING	SLEE[%d]: slee_acs(%d) WARNING: Configuration %s %d not found, using defaults	No acsTriggerIF configuration settings.	Check the configuration file contents, then restart the SLEE.	ACS
111243	ERROR	SLEE[%d]: slee_acs(%d) ERROR: Failed to register AcsTriggerChassisAction	Internal software error.	Contact support. No further information can be obtained.	ACS
111244	ERROR	SLEE[%d]: slee_acs(%d) ERROR: AcsTriggerChassisAction: failed to get SLEE Application API	Internal software error.	Contact support. No further information can be obtained.	ACS
111245	ERROR	SLEE[%d]: slee_acs(%d) ERROR: AcsTriggerChassisAction: failed to get handle for SLEE interface %s %d	The acsTriggerIF SLEE interface name was not found in SLEE configuration.	Check the configuration file contents, then restart the SLEE.	ACS
111246	ERROR	SLEE[%d]: slee_acs(%d) AcsTriggerChassisAction: failed to delete tag %d in block %d after trigger	Failed to delete a profile tag after a trigger event.	Check deleteTagsAfterTrigger configuration setting.	ACS
111247	CRITICAL	acsTriggerIF(%d) Unrecoverable exception: %s %d	Internal software error.	Contact support. No further information can be obtained.	ACS
111248	CRITICAL	acsTriggerIF(%d) Uncaught exception: %s %d	Internal software error.	Contact support. No further information can be obtained.	ACS
111249	ERROR	acsTriggerIF(%d) Failed to load config file: %s %d	The configuration file is missing or unreadable.	Check the configuration file status and permissions, then restart the SLEE.	ACS
111250	ERROR	acsTriggerIF(%d) Failed to send IDP: %s %d	Detail provided by alarm text.	Contact support.	ACS

Alarm	Severity	Text	Cause	Resolution	Service
111251	CRITICAL	slee_acs(%d) acsCallInitiationAction::classIn it: scf(LocalAddress) global title is compulsory in acs.conf for CAP4 ssfs.	Detail provided by alarm text.	Make sure the acs.conf file on the CP contains an scf entry for LocalAddress, with a global title.	ACS
111252	ERROR	%z Error reading table ACS_SUBURB_TYPE/ACS_SUBURB_TYPE_ MAPPING sqlcode %d: %s %d	Detail provided by alarm text.	Contact Support	ACS
111253	ERROR	DEF123 slee_acs(%d) ERROR: Invalid call %z time in session time information from %z	Unable to get session time information from IDP extension field.	Contact support.	ACS
111254	NOTICE	DEF123 slee_acs(%d) NOTICE: Unsupported session time information combination for %z	Information only.	No resolution.	ACS