

Policy Management

Policy Wizard Reference



Release 15.1
G61280-01
August 2026

ORACLE®

Copyright © 2014, 2026, Oracle and/or its affiliates.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software, software documentation, data (as defined in the Federal Acquisition Regulation), or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs) and Oracle computer documentation or other Oracle data delivered to or accessed by U.S. Government end users are "commercial computer software," "commercial computer software documentation," or "limited rights data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, reproduction, duplication, release, display, disclosure, modification, preparation of derivative works, and/or adaptation of i) Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs), ii) Oracle computer documentation and/or iii) other Oracle data, is subject to the rights and limitations specified in the license contained in the applicable contract. The terms governing the U.S. Government's use of Oracle cloud services are defined by the applicable contract for such services. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle®, Java, and MySQL are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Inside are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Epyc, and the AMD logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

Contents

About This Guide

Introduction to the Policy Wizard	xxiv
How This Guide is Organized	xxiv
Scope and Audience	xxvi
Related Publications	xxvi
Locate Product Documentation on the Oracle Help Center Site	xxvii
Customer Training	xxviii
My Oracle Support	xxviii
Emergency Response	xxviii

1 The Oracle Communications Configuration Management Platform Server

Configuration Management Platform Server	1-1
Specifications for Using the CMP Server	1-1
Logging In	1-2
CMP Interface Overview	1-3
CMP Icons	1-4
Shortcut Selection Keys	1-5
Changing a Password	1-6

Part I Using the Policy Wizard

2 Managing Policy Rules

3 Creating a Policy Rule

4	Parameters Within Policy Rules	
	QoS Values for Policy Conditions and Actions	4-1
5	Modifying and Deleting a Policy Rule	
	Modifying a Policy Rule	5-1
	Deleting a Policy Rule	5-1
6	About Policies	
	Understanding Policy Rules	6-1
	About Creating and Using Policies	6-2
	Structure and Evaluation of Policy Rules	6-2
	Structure of Policy Rules	6-2
	Policy Parameters	6-2
	Policy Logical Operators	6-3
	Parent and Reference Policies	6-4
	Evaluating Policy Rules	6-4
	Activating and Deactivating Policy Rules	6-6
	Using Reference Policies	6-7
	Modes and the Policy Wizard	6-8
7	Deploying Policies	
	About Deploying Policies	7-1
	Deploying a Policy	7-3
	Changing the Sequence of Deployed Policies on an MPE Device	7-4
	Removing a Policy from an MPE Device	7-5
8	Managing the Policy Library	
	Displaying a Policy	8-1
	Organizing Policies	8-2
	Importing and Exporting Policies, Policy Groups, and Templates	8-2
9	Managing Policy Tables	
	About Policy Tables	9-1
	About Data Matching	9-3
	Policy Matching Operations	9-3
	Example of Data Matching	9-4

Policy Table Case Study	9-6
Creating a Policy Table	9-10
Viewing Policy Tables	9-13
Associating a Policy Table with a Policy Rule	9-13
Associating a Parameter with a Policy Table Column	9-15
Modifying a Policy Table	9-15
Deleting a Policy Table	9-16

10 Managing Policy Groups

Creating a Policy Group	10-1
Adding a Policy or a Policy Group to a Policy Group	10-1
Displaying Details of All Policies in a Policy Group	10-2
Changing the Sequence of Policies or Policy Groups Within a Policy Group	10-3
Removing a Policy from a Policy Group	10-4
Managing Analytics Data Stream Generation for a Policy Group	10-5
Deleting a Policy Group	10-5

11 Managing Policy Templates

Creating a Policy Template	11-1
Modifying a Policy Template	11-1
Deleting a Policy Template	11-2

12 Managing Virtual Policy Tables

About Virtual Policy Tables	12-1
Virtual Policy Table Case Study	12-2
Creating a Virtual Policy Table	12-3
Modifying Virtual Policy Tables	12-4
Deleting Virtual Policy Tables	12-4

13 Managing Policy Checkpoints

About Policy Checkpoints	13-1
Creating a Policy Checkpoint	13-2
Viewing and Comparing Policy Checkpoints	13-2
Restoring a Policy Checkpoint	13-3
Restoring a Policy Checkpoint to MPE Devices	13-3
Deleting a Policy Checkpoint	13-4

Part II Configuring Manageable Objects for Use In Policies

14 About Creating Manageable Objects

Wireless Mode Objects	14-1
Cable Mode Objects	14-2
Wireline Mode Object	14-3

15 Managing Application Profiles

About Application Profiles	15-1
Creating an Application Profile	15-1
Modifying an Application Profile	15-2
Deleting an Application Profile	15-3

16 Managing Custom AVPs

About Custom AVPs	16-1
Creating an AVP	16-2
Modifying an AVP	16-6
Deleting an AVP	16-7

17 Managing Custom Vendors

About Custom Vendors	17-1
Creating a Custom Vendor	17-1
Modifying a Custom Vendor	17-2
Deleting a Custom Vendor	17-2

18 Managing Custom VSAs

About Custom VSAs	18-1
Creating a Custom VSA	18-1
Modifying a Custom VSA	18-3
Deleting a Custom VSA	18-3

19 Managing Match Lists

About Match Lists	19-1
Creating a Match List	19-1
Modifying a Match List	19-2

Deleting a Match List	19-3

20 Managing Media Profiles

About Media Profiles	20-1
Predefined Media Profiles	20-1
Creating a Media Profile	20-3
Modifying a Media Profile	20-4
Deleting a Media Profile	20-5

21 Managing Monitoring Keys

About Monitoring Keys	21-1
Creating a Monitoring Key	21-2
Modifying a Monitoring Key	21-2
Deleting a Monitoring Key	21-3

22 Managing Notification Servers

About Notification Servers	22-1
Creating a Notification Server	22-1
Enabling Notification on an MPE device	22-2
Viewing a Notification Server	22-2
Modifying a Notification Server	22-3
Associating a Notification Server with an MPE device	22-3
Associating a Notification Server with a Configuration Template	22-4
Removing the Notification Server Association with an MPE device	22-5
Deleting a Notification Server	22-6

23 Managing Policy Counter Identifiers

About Policy Counter IDs	23-1
Creating a Policy Counter ID	23-1
Modifying a Policy Counter ID	23-2
Deleting a Policy Counter ID	23-2
Policy Counter ID Groups	23-3
Creating a Policy Counter ID Group	23-3
Adding a Policy Counter ID to a Policy Counter ID Group	23-3
Modifying a Policy Counter ID Group	23-4
Deleting a Policy Counter ID from a Policy Counter ID Group	23-4
Deleting a Policy Counter ID Group	23-4

24 Managing Policy Time Periods

About Policy Time Periods	24-1
Creating a Time Period	24-2
Modifying a Time Period	24-4
Deleting a Time Period	24-4
About Time-of-Day Triggers	24-5

25 Managing Presence Reporting Area Lists

About Presence Reporting Area Lists	25-1
Presence Reporting Area List Case Study	25-1
Creating a Core Network Pre-Configured Presence Reporting Area List	25-2
Creating a UE-dedicated Presence Reporting Area List	25-2
Area List Type-Value Combinations	25-3
Modifying a Presence Reporting Area List	25-4
Deleting a Presence Reporting Area List	25-4

26 Managing Quotas

About Quotas	26-1
About Quota Plans	26-1
Creating a Plan	26-1
Modifying a Plan	26-6
Deleting a Plan	26-6
Example: Creating and Using a Plan	26-7
About Quota Passes	26-7
Creating a Pass	26-8
Modifying a Pass	26-11
Deleting a Pass	26-12
Creating a Pass Group	26-12
Adding a Pass to a Pass Group	26-13
Modifying a Pass Group	26-13
Removing a Pass from a Pass Group	26-14
Deleting a Pass Group	26-14

27 Managing Quota Conventions

About Quota Conventions	27-1
Creating a Quota Convention	27-2
Modifying a Quota Convention	27-3
Associating a Quota Convention with a Plan	27-4

Deleting a Quota Convention	27-4

28 Managing RADIUS CoA Templates

About RADIUS CoA Templates	28-1
Creating a RADIUS CoA Template	28-2
Modifying a RADIUS CoA Template	28-4
Deleting a RADIUS CoA Template	28-4
Example of Creating and Using a RADIUS CoA Template	28-4

29 Managing Retry Profiles

About Retry Profiles	29-1
Creating a Retry Profile	29-1
Modifying a Retry Profile	29-3
Deleting a Retry Profile	29-4

30 Managing Roaming Profiles

About Roaming Profiles	30-1
Creating a Roaming Profile	30-1
Modifying a Roaming Profile	30-4
Deleting a Roaming Profile	30-5

31 Managing Service Classes

About Service Classes	31-1
Creating a Service Class	31-1
Modifying a Service Class	31-3
Deleting a Service Class	31-3

32 Managing Services and Rating Groups

About Services	32-1
Creating a Service	32-1
Modifying a Service	32-2
Deleting a Service	32-2
About Rating Groups	32-3
Creating a Rating Group	32-3
Adding a Service to a Rating Group	32-3
Modifying a Rating Group	32-4
Removing a Service from a Rating Group	32-4

33 Managing Traffic Profiles

About Traffic Profiles	33-1
About Traffic Profile Variables	33-2
Example Traffic Profile Variables	33-3
Creating a Wireless Traffic Profile	33-3
ADC Rule Traffic Profile Configuration Parameters	33-5
Diameter QoS Traffic Profile Configuration Parameters	33-7
PCC Profile Traffic Profile Configuration Parameters	33-9
Predefined PCC Rule Extension Traffic Profile Configuration Parameters	33-12
PCC Rule Traffic Profile Configuration Parameters	33-13
Predefined ADC Rule Traffic Profile Configuration Parameters	33-17
Predefined ADC Rule Base Traffic Profile Configuration Parameters	33-17
Predefined PCC Rule Traffic Profile Configuration Parameters	33-18
Predefined PCC Rule Base Traffic Profile Configuration Parameters	33-18
SCE Profile Traffic Profile Configuration Parameters	33-19
QoS Values for Traffic Profiles	33-19
Creating a Cable Traffic Profile	33-19
Best Effort Traffic Profile Configuration Parameters	33-21
Diameter QoS Traffic Profile Configuration Parameters	33-22
Downstream Traffic Profile Configuration Parameters	33-23
Non-Real-Time Polling Traffic Profile Configuration Parameters	33-25
RSVP Flow Spec Traffic Profile Configuration Parameters	33-26
Real-Time Polling Traffic Profile Configuration Parameters	33-26
Unsolicited Grant Traffic Profile Configuration Parameters	33-27
Unsolicited Grant with Activity Detection Traffic Profile Configuration Parameters	33-28
Deploying a Traffic Profile	33-29
Modifying a Traffic Profile	33-30
Deleting a Traffic Profile	33-30
About Traffic Profile Groups	33-31
Creating a Traffic Profile Group	33-31
Adding a Traffic Profile to a Traffic Profile Group	33-31
Modifying a Traffic Profile Group	33-32
Removing a Traffic Profile from a Traffic Profile Group	33-32
Deleting a Traffic Profile Group	33-33

34 Managing Subscriber Keys

About Subscriber Keys	34-1

Creating a Subscriber Key	34-2
Modifying a Subscriber Key	34-3
Deleting a Subscriber Key	34-3

Part III Writing Policy Rules: Conditions, Actions, and Variables Reference

35 Conditions for Writing Policy Rules

Policy Condition Categories	35-1
Application Conditions	35-3
where AMID is the application manager ID	35-3
where AppType is the application type	35-3
where the application is latency sensitive	35-4
where the application is one of specified name	35-4
where the application will be using greater than # and less than # bps specified class of bandwidth	35-5
where the application will be using greater than # and less than # downstream sessions	35-6
where the application will be using greater than # and less than # specified class of sessions	35-7
where the application will be using greater than # bps of specified class of bandwidth	35-7
where the application will be using greater than # bps upstream reserved bandwidth	35-8
where the application will be using greater than # bps upstream reserved bandwidth	35-10
where the application will be using greater than # sessions	35-11
where the application will be using greater than # specified class of sessions	35-11
where the application will be using greater than # upstream reserved flows	35-12
where there is no application associated with the request	35-13
Device Usage Conditions	35-14
where the device will be handling greater than # and less than # bps of specified class of bandwidth	35-14
where the device will be handling greater than # and less than # bps of specified class of sessions	35-15
where the device will be handling greater than # and less than # percent of downstream capacity	35-16
where the device will be handling greater than # and less than # specified class of sessions	35-17
where the device will be handling greater than # bps downstream bandwidth	35-17
where the device will be handling greater than # bps of specified class of bandwidth	35-18
where the device will be handling greater than # bps reserved bandwidth in total for specified class of traffic	35-19
where the device will be handling greater than # bps upstream reserved bandwidth	35-21
where the device will be handling greater than # bps upstream reserved bandwidth in total for specified application	35-23
where the device will be handling greater than # downstream sessions	35-25

where the device will be handling greater than # percent of downstream capacity	35-25
where the device will be handling greater than # percent of reserved capacity for specified class of traffic	35-26
where the device will be handling greater than # percent of upstream reserved capacity	35-28
where the device will be handling greater than # percent of upstream reserved capacity for specified application	35-29
where the device will be handling greater than # reserved flows in total for specified class of traffic	35-31
where the device will be handling greater than # specified class of sessions	35-33
where the device will be handling greater than # upstream reserved flows	35-34
where the device will be handling greater than # upstream reserved flows in total for specified application	35-35
Mobility Conditions	35-37
where network initiated requests are supported	35-37
where the APN matches one of specified APN value(s)	35-37
where the BSID matches one of specified Bsid value(s)	35-38
where the Cell Identifier matches one of specified CI value(s)	35-39
where the cell state is specified	35-39
where the CSG Access Mode is closed	35-40
where the CSG ID is available	35-40
where the CSG ID matches one of specified CSG ID values(s)	35-41
where the E-UTRAN Cell Identifier matches one of specified ECI value(s)	35-41
where the IP address of the Serving Gateway matches one of specified address(es)	35-42
where the IP address of the Serving PCF matches one of specified address(es)	35-43
where the IP-CAN type is specified	35-43
where the Location Area Code matches one of specified LAC value(s)	35-44
where the mobile session supports sponsored connectivity	35-45
where the MSTimezone DST is configured daylight savings in hours	35-46
where the MSTimezone offset is configured timezone offset	35-46
where the RAT type is specified	35-47
where the Routing Area Code matches one of specified RAC value(s)	35-48
where the Routing Area Identifier matches one of specified RAI value(s)	35-49
where the Service Area Code matches one of specified SAC value(s)	35-49
where the Serving MCC-MNC matches one of specified MCC-MNC value(s)	35-50
where the subscribed PRA area matches one of specified PRA area(s)	35-51
where the Tracking Area Code matches one of specified TAC value(s)	35-52
where the UE is inside/outside/inactive subscribed PRA area for any one of specified PRA area(s)	35-53
where the UE is member of the CSG	35-54
Network Device Conditions	35-55
where # is the CMTS blade index	35-55
where # is the CMTS channel index	35-55

where the An-Gw status is active	35-56
where the cable modem IP address is in specified subnet	35-56
where the cable modem IP address is specified address	35-57
where the cable modem MAC address is specified address	35-57
where the device name matches one of specified name(s)	35-58
where the device type is specified type	35-59
where the endpoint IP address is in specified subnet	35-60
where the endpoint IP address is specified address	35-60
where the network element name matches one of specified name(s)	35-61
where the network element type is specified type	35-62
where the network element's description field is equal to specified description(s)	35-63
where the network element's diameter identity matches one of specified description(s)	35-63
where the remote MPE is unavailable	35-64
where the request is not using the cable modem IP address	35-65
where the request is using the cable modem IP address	35-65
where the User Equipment ESN matches one of specified ESN value(s)	35-65
where the User Equipment IMEISV matches one of specified IMEISV value(s)	35-66
where the User Equipment MAC matches one of specified MAC value(s)	35-67
where the User Equipment MEID matches one of specified MEID value(s)	35-67
Notification Conditions	35-68
where notification from Sh datasource is received for User Profile	35-69
Policy Context Properties Conditions	35-71
where the policy context property name exists	35-71
where the policy context property name is numerically equal to value	35-72
where the policy context property name matches one of `value(s)`	35-73
Policy Method Conditions	35-74
where evaluate the customized method specified name(s)	35-74
Policy Counters Conditions	35-74
where a current status exists for Policy Counter IDs select names	35-74
where the Filter-Ids for Policy Counter ID select name current status match one or more of Filter-Ids to match	35-75
where the Final-Unit-Action for Policy Counter IDs select names current status matches Final-Unit-Action to match	35-76
where the Final-Unit-Indication AVP for Policy Counter IDs select names current status exists	35-77
where the Policy Counter ID select name current status is between value and value	35-78
where the Policy Counter ID select name current status is contained in Match Lists select lists	35-80
where the Policy Counter ID select name current status is numerically equal to value	35-81
where the Policy Counter ID select name current status matches one of specified value(s)	35-82
where the Policy Counter ID select name status is equal to default status	35-83

where the Policy Counter IDs select names exists	35-84
where the Sy Session exists	35-84
Policy SDP Properties Conditions	35-85
where the local codec data is an offer	35-85
where the local specified SDP property exists	35-86
where the local specified SDP property is numerically equal to value	35-88
where the local specified SDP property matches one of value(s)	35-91
RADIUS Conditions	35-94
where the BNG COA destination port is port number	35-94
where the RADIUS accounting request is RADIUS Accounting-Start	35-94
where the RADIUS request contains a TLV / VSA of name or ID	35-95
where the RADIUS request contains TLV / VSA name or ID whose value is contained in Match List List of TLV / VSA value as string	35-96
where the RADIUS request contains TLV / VSA name or ID whose value is numerically equal to number	35-97
where the RADIUS request contains TLV / VSA name or ID whose value matches one of TLV / VSA value as string	35-98
where the RADIUS request contains VSAs from vendor	35-99
Request Conditions	35-100
where at least one Filter-ID AVP exists	35-100
where at least one Final-Unit-Action matches Final-Unit-Action to match	35-100
where at least one Final-Unit-Indication AVP exists	35-101
where at least one flow has media type that matches specified type(s)	35-101
where at least one flow with media type specified type(s) has one of the statuses specified status(s)	35-102
where Filter-ID AVP does not exist	35-104
where Final-Unit-Indication AVP does not exist	35-104
where the AF-Application-ID is available	35-104
where the AF-Application-ID matches one of specified value(s)	35-105
where the Application-Service-Provider-Identity matches one of specified Application Service Provider Identity(s)	35-105
where the bearer usage is General	35-106
where the Classifier parameters are equal to specified value	35-107
where the codec name for the flow matches one of specified codec name(s)	35-108
where the corresponding enforcement session supports feature name	35-109
where the DPI session is a Gx Lite session	35-109
where the enforcement session is an IP-CAN session	35-110
where the event trigger is one of specified trigger(s)	35-111
where the Filter-Ids in the Final-Unit-Indication AVPs match one or more of Filter-Ids to match and the search type is search type	35-113
where the flow has greater than # grants per interval	35-114
where the flow is an application flow	35-115
where the flow media type is one of specified type(s)	35-115

where the flow media type matches one of user defined media type(s)	35-116
where the flow media type specified type(s) is one of specified status(s)	35-117
where the flow packet filter matches one of specified packet filter(s)	35-118
where the flow usage is one of specified usage(s)	35-119
where the IP-CAN bearer is the primary bearer	35-119
where the names of the installed PCC/ADC rule contains one of specified PCC/ADC rule names	35-120
where the PCC rule being reinstalled contains one of specified rule name(s) and the retry is the final attempt	35-121
where the PCC/ADC rule being reinstalled contains one of specified rule name(s) and the retry is the final attempt	35-121
where the protocol being executed is PCMM	35-122
where the QoS parameters in the flow are equal to specified value	35-123
where the QoS upgrade is supported	35-123
where the quota is requested	35-124
where the quota usage rating conditions changed trigger is one of specified values	35-124
where the quota usage reporting reason is one of specified values	35-126
where the RAN-NAS-Release-Cause is Protocol Type and Cause Type	35-127
where the reauth is triggered by subscriber profile update with notification type specified type(s)	35-128
where the reauth request is triggered by scheduled task containing Service key with action	35-129
where the reauthorization reason is REASON_REVALIDATION_TIMEOUT	35-130
where the reauthorization reason is specified value	35-131
where the request AVP Media-Component-Description exists	35-132
where the request AVP name exists	35-132
where the request AVP name value contains one of value(s)	35-133
where the request AVP name value is contained in Match Lists select lists	35-134
where the request AVP name value is numerically equal to value	35-135
where the request AVP name value matches one of value(s)	35-137
where the request Credit Management Status is one of specified type(s)	35-138
where the request is creating a new flow	35-139
where the request is creating a new session	35-139
where the request is for downstream bandwidth	35-140
where the request is for reserved bandwidth	35-141
where the request is for specified class of traffic	35-141
where the request is for upstream bandwidth	35-142
where the request is reporting session quota usage	35-143
where the request MPS Identifier matches one of value(s)	35-143
where the request supports feature name	35-144
where the requested downstream bandwidth is greater than # and less than # bps	35-145
where the requested GCS Identifier matches one of value(s)	35-146

where the requested guaranteed downstream bandwidth is greater than # bps	35-146
where the requested guaranteed upstream bandwidth is greater than # bps	35-147
where the requested maximum upstream bandwidth is greater than specified bps	35-149
where the requested media component description reservation priority is one of specified	35-150
where the requested minimum upstream bandwidth is greater than specified bps	35-151
where the requested QCI is one of specified	35-153
where the requested quota is one of select quota	35-154
where the requested rating group is one of select rating group	35-154
where the requested service class matches one of specified name(s)	35-155
where the requested services are select service	35-155
where the requested session reservation priority is one of specified	35-156
where the requested time limit is greater than # seconds	35-157
where the requested time limit is unlimited (or unspecified)	35-158
where the requested upstream APN aggregate maximum bitrate is greater than # bps	35-158
where the requested volume limit is greater than # kilobytes	35-159
where the requested volume limit is unlimited or unspecified	35-160
where the Required-Access-Info matches one of value(s)	35-161
where the roaming profile for the session is one of Roaming Profile name	35-161
where the rule report contains one of specified rule name(s) and the final unit action is one of specified values and the rule status is active	35-162
where the rule report contains one of specified rule name(s) and the rule status is active	35-163
where the rule report contains one of specified rule name(s) and the rule status is active and the rule failure code is one of specified failure code(s)	35-164
where the rule report contains one of specified rule name(s) and the rule status is active and the rule failure code is one of specified failure code(s) and the maximum retry count is reached	35-166
where the rule report contains RAN-NAS-Release-Cause and is Protocol Type and Cause Type	35-168
where the rule report for the flow has status active	35-169
where the select type is contained in Match Lists select lists	35-169
where the select type is not contained in Match Lists select lists	35-171
where the service info status is one of specified	35-173
where the Service-URN is one of specified value(s)	35-174
where the session is an enforcement session	35-174
where the SessionClassID is specified value	35-175
where the specific action is one of specified action(s)	35-175
where the Sponsor-Identity matches one of specified Sponsor Identity(s)	35-176
where the TDF-Application-Identifier matches one of specified TDF application id(s)	35-177
where the user field field is available	35-178
where top-up instance being granted for select type using monitoring key is valid	35-178
where the AF-Requested-Data AVP exists and indicates select type(s)	35-179

State Variables Conditions	35-180
where the last delivery time of specific use case exists in the user state variable of LastDeliveryTime	35-180
where the scope state variable name + 0 days rounded up with same granularity is after now using configured local time	35-181
where the scope state variable name exists	35-185
where the scope state variable name is in the current billing cycle using configured local time	35-186
where the scope state variable name is numerically equal to value	35-187
where the scope state variable name is the current mobile country code	35-189
where the scope state variable name matches one of `value(s)`	35-190
where the scope state variable name value is contained in Match Lists selected lists	35-191
Time of Day Conditions	35-193
where the current time is between start time and end time using configured local time	35-193
where the current time is within the specified time period(s)	35-194
where today is a week day using configured local time	35-195
where today is a weekend day using configured local time	35-195
where today is day using configured local time	35-196
where today is the specified number(s) th day(s) of Any Month in natural order using configured local time	35-197
User Conditions	35-199
where the account id matches one of specified id(s)	35-199
where the account will be handling greater than # and less than # percent of downstream limit	35-200
where the account will be handling greater than # percent of downstream limit	35-201
where the account will be handling greater than # percent of upstream reserved limit	35-201
where the account will be using greater than # and less than # bps downstream bandwidth	35-203
where the account will be using greater than # and less than # downstream sessions	35-204
where the account will be using greater than # bps downstream bandwidth	35-205
where the account will be using greater than # bps of specified class of bandwidth	35-206
where the account will be using greater than # bps reserved bandwidth in total for specified class of traffic	35-206
where the account will be using greater than # bps upstream bandwidth in total for specified application	35-208
where the account will be using greater than # bps upstream reserved bandwidth	35-210
where the account will be using greater than # downstream sessions	35-211
where the account will be using greater than # reserved flows in total for specified class of traffic	35-212
where the account will be using greater than # specified class of sessions	35-214
where the account will be using greater than # upstream flows in total for specified application	35-215
where the account will be using greater than # upstream reserved flows	35-216
where the pool type is basic	35-217

where the subscriber or pool does not have any of the named entitlements	35-218
where the subscriber or pool does not have at least one of the named entitlements	35-219
where the subscriber or pool field + 0 days rounded up with same granularity is after now using configured local time	35-220
where the subscriber or pool field exists	35-223
where the subscriber or pool field is in the current billing cycle using configured local time	35-224
where the subscriber or pool field is modified via notification	35-225
where the subscriber or pool field is numerically equal to value	35-226
where the subscriber or pool field matches one of specified value(s)	35-228
where the subscriber or pool field prior to notification matches one of specified value(s)	35-229
where the subscriber or pool has all of the named entitlements	35-230
where the subscriber or pool has at least one of the named entitlements	35-231
where the subscriber or pool profile data is available	35-232
where the subscriber profile data expiration timestamp field for day pass in millis is less than hours from expiration hours from expiring	35-232
where the tier is one of specified tier(s)	35-233
where the tier will be handling greater than # and less than # specified class of sessions	35-234
where the tier will be handling greater than # specified class of sessions	35-235
where the tier will be using greater than # and less than # bps of specified class of bandwidth	35-235
where the tier will be using greater than # bps of specified class of bandwidth	35-237
where the user E.164 phone number matches one of specified number(s)	35-237
where the user has greater than # of passes named select type	35-238
where the user has greater than # of rollover units of type unit type for plan plan name and usage usage type	35-239
where the user has greater than # of top-ups for plan select type	35-241
where the user IMSI matches one of specified number(s)	35-242
where the user is a home user	35-243
where the user is using greater than # percent and less than # percent select type of dynamic quota for selected	35-243
where the user is using greater than # percent select type of dynamic quota for selected	35-245
where the user is using greater than # seconds in total for selected quota	35-246
where the user is using greater than # service-specific units for selected quota	35-248
where the user is using greater than # units of total volume (bytes) for selected quota	35-249
where the user is using greater than specified percent and less than # percent of select type for selected quota	35-250
where the user is using greater than specified percent of select type for selected quota	35-252
where the user NAI matches one of specified id(s)	35-254
where the user realm matches one of specified realm(s)	35-254
where the user Service key exists	35-255

where the user Service key field contains one of specified value(s)	35-256
where the user Service key field matches one of value(s)	35-257
where the user Service key field prior to notification matches one of previous value	35-259
where the user Service key is in the activation timeframe using configured local time	35-260
where the user SIP URI matches one of specified URI(s)	35-261
where the user will be handling greater than # percent of upstream reserved limit	35-262
where the user will be using greater than # bps reserved bandwidth in total for specified class of traffic	35-264
where the user will be using greater than # bps upstream reserved bandwidth	35-266
where the user will be using greater than # bps upstream reserved bandwidth in total for specified application	35-267
where the user will be using greater than # upstream reserved flows	35-269
where the user will be using greater than # upstream reserved flows in total for specified application	35-271
where the User's Tier downstream bandwidth limit is between # bps and # bps	35-273
where the User's Tier downstream bandwidth limit is greater than # bps	35-274
where the User's Tier upstream bandwidth limit is between # bps and # bps	35-275
where the User's Tier upstream bandwidth limit is greater than # bps	35-276

36 Actions for Writing Policy Rules

Mandatory Policy-Processing Actions	36-1
accept message	36-1
break from policy level	36-2
continue processing message	36-2
reject message	36-2
reject message with code `number`	36-3
reject message with code `number`	36-3
reject message with Experimental-Result-Code `number` and Vendor-ID `number`	36-4
skip to next device	36-5
skip to next flow	36-5
Optional Policy-Processing Actions	36-5
add custom grouped AVP name and send always	36-6
add the APP Detection Flow select scope to specified PCC rules	36-7
Advanced: set values for QoS and Charging parameters to specified value	36-8
apply roaming profile name	36-10
apply specified profile(s) to all flows in the request	36-10
apply specified profile(s) to request	36-11
apply specified profiles to flow(s) whose media type matches one of specified types	36-12
apply specified profiles to selected specified types flows in the request	36-13
clear alarm with severity `severity level`, id `unique alarm identifier` and message `message text`	36-14

disable forwarding to next hop gateway	36-15
disable monitoring key	36-15
disable VLAN tagging	36-16
enable event messaging for this request	36-16
enable forwarding to next hop gateway with address none	36-17
enable subscription for notification of user profile changes	36-17
enable subtracting usage from select quota for monitoring key	36-17
enable VLAN tagging with Id specified	36-19
enable/disable PRA subscription	36-19
establish traffic detection session using the IP-CAN TDF information	36-20
establish traffic detection session with select network element identity	36-20
evaluate policy group select policy group	36-21
evaluate policy select policy	36-22
evaluate the schedule task on Service	36-22
fetch Policy Counters default from OCS	36-23
grant # bytes for quota	36-24
grant # of select units for select quota	36-24
grant # percent in service-specific units for quota	36-25
grant # percent in time for quota	36-26
grant # percent in volume for quota	36-26
grant # percent of select type for BEST OF select quota	36-27
grant # percent of select type for select quota	36-28
grant # seconds for quota	36-30
grant # service-specific units for quota	36-30
grant # units of total volume (bytes) for select quota	36-31
grant # units of total volume (bytes) for select quota using monitoring key	36-32
grant session time limit to specified percent of select quota	36-34
grant total volume to specified percent used for BEST OF select quota	36-34
grant total volume to specified percent used for BEST OF select quota using monitoring key	36-36
grant total volume to specified percent used for select quota	36-38
grant total volume to specified percent used for select quota using monitoring key	36-40
install PRA change for PRA area(s)	36-42
install specified ADC rule(s) for select scope	36-43
install specified ADC rule(s) for select scope active between start time and end time	36-44
install specified ADC rule(s) for select scope active within Time Period	36-46
install specified ADC rule(s) for select scope for specified retry profile active between start time and end time	36-47
install specified ADC rule(s) for select scope for specified retry profile active within Time Period	36-49
install specified ADC rule(s) for select scope with specified retry profile	36-50
install specified PCC rule(s) for select scope	36-51

install specified PCC rule(s) for select scope active between start time and end time	36-52
install specified PCC rule(s) for select scope active within Time Period	36-54
install specified PCC rule(s) for select scope for specified retry profile active between start time and end time	36-55
install specified PCC rule(s) for select scope for specified retry profile active within Time Period	36-57
install specified PCC rule(s) for select scope with specified retry profile	36-59
mark request AVP name as failed if exists and send always	36-60
overwrite Conditional Policy Information with Execution-Time to time and parameters specified	36-61
overwrite DSCP/TOS field with #	36-64
overwrite SessionClassId with #	36-65
re-authorize all credit control sessions associated with User	36-65
re-authorize all PCEF/TDF sessions associated with select scope	36-66
release all credit control sessions associated with User	36-67
release all PCEF/TDF sessions associated with select scope	36-67
release the session	36-68
release the session with cause `ReleaseCause`	36-68
remove ADC rule type(s) select types of rules for select scope	36-68
remove all policy context properties	36-69
remove all the scope state variables and save always	36-70
remove Conditional Policy Information(s)	36-71
remove custom AVP name from reply always	36-71
remove default PCC rules of default TDF application IDs for APPLICATION_STOP	36-72
remove PCC rule for the flow	36-74
remove PCC rule type(s) select types of rules for select scope	36-74
remove policy context property name	36-75
remove PRA change for PRA area(s)	36-75
remove specified ADC rule(s)	36-77
remove specified PCC rule(s)	36-77
remove the scope state variable name and save always	36-78
request usage report for monitoring key	36-79
reset all plan usage	36-80
reset all plan usage with reset type of select reset type	36-80
reset all subscriber data	36-81
reset select quota reset type of select reset type	36-81
reset the last delivery time of specific use case(s) in the user state variable of LastDeliveryTime	36-82
reset usage for select quota	36-83
revalidate the session at datetime using configured local time	36-84
schedule next RAR for resetting usage for select quota	36-85
send CoA with COA Template	36-85

send http POST notification to select notification destination with headers headers and content content	36-86
send http POST notification to url URL with headers headers and content content	36-88
send notification to syslog with `message text` and severity `severity level`	36-91
send notification to trace log with `message text` and severity `severity level`	36-92
send SMS Alert `specified` to user	36-93
send SMS `specified` to `default` destination address, `default` TON and `default` NPI from `default` source address, `default` TON and `default` NPI on `now`. Request delivery receipt `default`. Select SMS Gateway `default`.	36-94
send SMS `specified` to `default` destination address, `default` TON and `default` NPI from `default` source address, `default` TON and `default` NPI on `Billing Day`. Request delivery receipt `default`. Select SMS Gateway `default`.	36-98
send SMS `specified` to `default` destination address, from `default` source address on user billing day. Request delivery receipt `default`. Select SMS Gateway `default`.	36-102
send SMS `specified` to `default` destination address, from `default` source address. Request delivery receipt `default`. Select SMS Gateway `default`.	36-105
send SMS `specified` to user from `default` source address if exceed `number` `days` for `Identity`. Request delivery receipt `default`. Select SMS Gateway `default`.	36-107
send SMS `specified` to user on `now`. Request delivery receipt `default`. Select SMS Gateway `default`.	36-109
send SMS `specified` to user on `Billing Day`. Request delivery receipt `default`. Select SMS Gateway `default`.	36-112
send SMS `specified` to user. Request delivery receipt `default`. Select SMS Gateway `default`.	36-115
send SMTP message with the following text/plain content	36-116
set alarm with severity `severity level`, id `unique alarm identifier` and message `message text`	36-119
set authorization validity time to # seconds	36-120
set authorization validity time to datetime	36-120
set authorization validity time to time on day using configured local time	36-121
set charging server(s) for the IP-CAN/Sd session to specified values	36-123
set CSG reporting info to select value	36-123
set custom AVP name value to the policy context property name	36-124
set custom AVP name value to the user property name and save always	36-125
set DRMP AVP to DRMP Level in Re-Authorized Request	36-126
set enterprise service path ID to value for the Gx session	36-127
set external field to # percent of select type for selected quota	36-127
set external field to `value`	36-129
set NoOptimization to request	36-130
set policy context property name to the instance name of dynamic quota of selected being used	36-130
set policy context property name to value	36-131
set Quota Exhaustion Action to specified	36-132
set session revalidation time to # seconds	36-133

set session revalidation time to Policy Counter ID(s) select name(s)	36-134
set session revalidation time to time on day using configured local time	36-134
set specified ARP to value	36-136
set the scope state variable name to now + 0 days rounded up with same granularity using configured local time and save always	36-136
set the scope state variable name to now using configured local time and save always	36-140
set the scope state variable name to property name + multiple of 0 days rounded up with same granularity and save always	36-142
set the scope state variable name to select traffic profile name and save always	36-145
set the scope state variable name to `value` and save always	36-146
set the scope state variable name to time plus random value within # seconds and save always	36-148
set the user property name to Existing or New custom AVP name and send always	36-151
set threshold to # percent of granted quota for service-specific units	36-152
set threshold to # percent of granted quota for time	36-153
set threshold to # percent of granted quota for volume	36-154
set time limit to # seconds	36-155
set value to Existing or New custom AVP name and send always	36-155
set volume limit to # kilobytes	36-157
set volume threshold to # bytes for select quota	36-157
subscribe PRA change for PRA area	36-158
unsubscribe PRA change	36-159

37 Policy Rule Variables

About This Guide

This chapter contains an overview of the manual, describes how to obtain help, where to find related documentation, and provides other general information.

Introduction to the Policy Wizard

This reference contains information about policies that you can create, deploy, and manage using the Oracle Communications Policy Management Configuration Management Platform (CMP) system in all operating modes. This reference describes the manageable objects you can include in policies, the policy wizard you use to create policies, and the policy conditions, actions, and variables available for your use in writing policy rules.

Conventions

The following conventions are used throughout this guide:

- **Bold text** in procedures indicates icons, buttons, links, or menu items that you can click.
- *Italic text* indicates variables.
- `Monospace text` indicates text displayed or text that you enter exactly as shown.

How This Guide is Organized

The information in this guide is presented in the following order:

- [About This Guide](#) provides general information about the organization of this guide, related documentation, and how to get technical assistance.
- [The Oracle Communications Configuration Management Platform Server](#) provides an overview of policies, policy groups, and the Oracle Communications Policy Management Configuration Management Platform (CMP) system, which lets you create, deploy, and manage policies and the objects that you can refer to or manipulate within them.
- Part I:
 - [About Policies](#) describes how policies are structured and evaluated, as well as how they can be used.
 - [Creating a Policy Rule](#) describes how to create policy rules.
 - [Deploying Policies](#) describes how to manage policy deployment.
 - [Managing the Policy Library](#) describes how to organize and manage your policy library.

- [Managing Policy Tables](#) describes how to create and manage your library of policy tables.
- [Managing Policy Groups](#) describes how to create and manage policy groups.
- [Managing Policy Templates](#) describes how to create and manage policy templates to simplify the creation of multiple policies with similar conditions and actions.
- [Managing Virtual Policy Tables](#) describes how to create and manage your library of virtual policy tables.
- [Managing Policy Checkpoints](#) describes the method of saving CMP objects and their configuration, as well as their association, to the CMP database at a specific point in time.
- Part II:
 - [About Creating Manageable Objects](#) describes the manageable objects that you can create in wireless, cable, and wireline modes.
 - [Managing Application Profiles](#) describes how to create and manage application profiles.
 - [Managing Custom AVPs](#) describes how to create and manage custom RADIUS attribute-value pairs (AVPs) in a wireless network.
 - [Managing Custom Vendors](#) describes how to create and manage custom RADIUS vendors in a wireless network.
 - [Managing Custom VSAs](#) describes how to create and manage custom RADIUS vendor-specific attributes (VSAs) in a wireless network.
 - [Managing Match Lists](#) describes how to manage match lists in a wireless network.
 - [Managing Media Profiles](#) describes how to create and manage media profiles in a cable network.
 - [Managing Monitoring Keys](#) describes how to create and manage monitoring keys in a wireless network.
 - [Managing Notification Servers](#) describes how to create and manage notification servers in the CMP system.
 - [Managing Policy Counter Identifiers](#) describes how to create and manage policy counter identifiers in a wireless network.
 - [Managing Policy Time Periods](#) describes how to create and manage policy time periods in a wireless network.
 - [Managing Presence Reporting Area Lists](#) describes how to create and manage Presence Reporting Area lists in a wireless network.
 - [Managing Quotas](#) describes how to create and manage Gx and Gy quotas in a wireless network.
 - [Managing Quota Conventions](#) describes how to create and manage quota conventions in a wireless network.
 - [Managing RADIUS CoA Templates](#) describes how to create, manage, and use RADIUS Change of Authorization (CoA) templates in a wireless network.
 - [Managing Retry Profiles](#) describes how to create and manage retry profiles in a wireless network.
 - [Managing Roaming Profiles](#) describes how to create and manage roaming profiles.

- [Managing Service Classes](#) describes how to create and manage service classes in a cable network.
- [Managing Services and Rating Groups](#) describes how to create and manage Gy services and rating groups in a wireless network.
- [Managing Subscriber Keys](#) describes how to create and manage RADIUS subscriber keys in a wireless network.
- [Managing Traffic Profiles](#) describes how to create and manage traffic profiles.
- Part III is a reference that describes the conditions, actions, and variables used when creating policy rules.

Scope and Audience

This document is intended for policy designers, who use the CMP system, particularly the policy wizard and the policy table wizard, to design, create, and deploy policy rules for a carrier network.

Related Publications

For information about additional publications related to this document, refer to the Oracle Help Center site. See [Locate Product Documentation on the Oracle Help Center Site](#) for more information on related product publications.

Policy and Protocol Specifications

The following specifications provide information on protocols:

- PCMM CableLabs specifications:
 - PKT-SP-MM-I05: PacketCable™ Multimedia Specification
 - PKT-SP-DQOS-I12-050812: PacketCable™ Dynamic Quality-of-Service Specification
- Internet Engineering Task Force (IETF) specifications:
 - RADIUS RFCs:
 - * RFC 2865: RADIUS
 - * RFC 2866: RADIUS Accounting
 - * RFC 3576: Dynamic Authorization Extensions to RADIUS
 - Diameter RFCs:
 - * RFC 3539: Authentication, Authorization and Accounting (AAA) Transport Profile
 - * RFC 3588: Diameter Base Protocol
 - TACACS+ RFC 1492: An Access Control Protocol, Sometimes Called TACACS
 - RFC 3164: The BSD syslog Protocol
- 3rd Generation Partnership Project (3GPP) technical specifications:
 - 3GPP TS 23.003: Numbering, addressing and identification (Release 12)

- 3GPP TS 23.203: Policy and charging control architecture (Release 13.2)
- 3GPP TS 26.114: IP Multimedia Subsystem (IMS); Multimedia telephony; Media handling and interaction (Release 13.1.0)
- 3GPP TS 26.445: Codec for Enhanced Voice Services (EVS); Detailed algorithmic description (Release 13.0.0)
- 3GPP TS 23.402: Architecture enhancements for non-3GPP accesses (Release 13)
- 3GPP TS 29.208: End-to-end Quality of Service (QoS) signalling flows (Release 6)
- 3GPP TS 29.209: Policy control over Gq interface (Release 6)
- 3GPP TS 29.211: Rx Interface and Rx/Gx signalling flows (Release 6)
- 3GPP TS 29.212: Policy and Charging Control over Gx/Sd reference point (Release 13.0)
- 3GPP TS 29.213: Policy and Charging Control signalling flows and QoS parameter mapping (Release 12.x6)
- 3GPP TS 29.214: Policy and Charging Control over Rx reference point (Release 13.0)
- 3GPP TS 29.219: Policy and Charging Control: Spending limit reporting over Sy reference point (Release 11.3)
- 3GPP TS 29.229: Cx and Dx interfaces based on the Diameter protocol; Protocol details (Release 8)
- 3GPP TS 29.273: Evolved Packet System (EPS); 3GPP EPS AAA interfaces (Release 12.6)
- 3GPP TS 32.240: Charging architecture and principles (Release 8)
- 3GPP TS 32.299: Telecommunication management; Charging management; Diameter charging applications (Release 8)
- 3rd Generation Partnership Project 2 (3GPP2) technical specifications:
 - 3GPP2 X.S0013-012-0: Service Based Bearer Control — Stage 2
 - 3GPP2 X.S0013-013-0: Service Based Bearer Control — Tx Interface Stage 3
 - 3GPP2 X.S0013-014-0: Service Based Bearer Control — Ty Interface Stage 3

Locate Product Documentation on the Oracle Help Center Site

Oracle Communications customer documentation is available on the web at the Oracle Help Center (OHC) site, <http://docs.oracle.com>. You do not have to register to access these documents. Viewing these files requires Adobe Acrobat Reader, which can be downloaded at <http://www.adobe.com>.

1. Access the Oracle Help Center site at <http://docs.oracle.com>.
2. Click `Industries`.
3. Under the Oracle Communications subheading, click the `Oracle Communications documentation` link.

The Communications Documentation page appears. Most products covered by these documentation sets will appear under the headings "Network Session Delivery and Control Infrastructure" or "Platforms."

4. Click on your Product and then the Release Number.

A list of the entire documentation set for the selected product and release appears.

5. To download a file to your location, right-click the PDF link, select `Save target as` (or similar command based on your browser), and save to a local folder.

Customer Training

Oracle University offers training for service providers and enterprises. Visit our web site to view, and register for, Oracle Communications training:

<http://education.oracle.com/communication>

To obtain contact phone numbers for countries or regions, visit the Oracle University Education web site:

www.oracle.com/education/contacts

My Oracle Support

My Oracle Support (<https://support.oracle.com>) is your initial point of contact for all product support and training needs. A representative at Customer Access Support can assist you with My Oracle Support registration.

Call the Customer Access Support main number at 1-800-223-1711 (toll-free in the US), or call the Oracle Support hotline for your local country from the list at <http://www.oracle.com/us/support/contact/index.html>. When calling, make the selections in the sequence shown below on the Support telephone menu:

- For Technical issues such as creating a new Service Request (SR), select **1**.
- For Non-technical issues such as registration or assistance with My Oracle Support, select **2**.
- For Hardware, Networking and Solaris Operating System Support, select **3**.

You are connected to a live agent who can assist you with My Oracle Support registration and opening a support ticket.

My Oracle Support is available 24 hours a day, 7 days a week, 365 days a year.

Emergency Response

In the event of a critical service situation, emergency response is offered by the Customer Access Support main number at 1-800-223-1711 (toll-free in the US), or by calling the Oracle Support hotline for your local country from the list at <http://www.oracle.com/us/support/contact/index.html>. The emergency response provides immediate coverage, automatic escalation, and other features to ensure that the critical situation is resolved as rapidly as possible.

A critical situation is defined as a problem with the installed equipment that severely affects service, traffic, or maintenance capabilities, and requires immediate corrective action. Critical situations affect service and/or system operation resulting in one or several of these situations:

- A total system failure that results in loss of all transaction processing capability
- Significant reduction in system capacity or traffic handling capability

- Loss of the system's ability to perform automatic system reconfiguration
- Inability to restart a processor or the system
- Corruption of system databases that requires service affecting corrective actions
- Loss of access for maintenance or recovery operations
- Loss of the system ability to provide any required critical or major trouble notification

Any other problem severely affecting service, capacity/traffic, billing, and maintenance capabilities may be defined as critical by prior discussion and agreement with Oracle.

List of Figures

1-1	Structure of the CMP Interface	1-3
3-1	Example of Selected Policy Conditions	3-3
3-2	Example of Parameter Option Selections	3-3
3-3	Example of Parameter Value Entry	3-4
3-4	Example of Selected Policy Actions	3-4
4-1	Example of a Parameter Pop-up	4-1
7-1	Policy Deployment	7-1
7-2	Policy Group Deployment	7-2
7-3	Policy Redeployment	7-3
7-4	Policy Server Selection Window	7-4
8-1	Sample Policy Description	8-1
9-1	Defining a Policy Table Key Column	9-2
9-2	Sample Policy Table	9-13
10-1	Policy within a Policy Group	10-4
10-2	Removing a Policy from a Policy Group	10-5
16-1	Sample AVP Definition	16-6
24-1	Example of Time Slot Overlap	24-3

List of Tables

4-1	QoS values for Policy Conditions	4-2
4-2	QoS values for Policy Actions	4-2
9-1	Example of a Policy Table	9-2
9-2	Quotas and Policy Names	9-6
9-3	Differences Between Quotas	9-9
12-1	Monthly Data Plans Policy Table	12-2
12-2	Four-tier Data Plans Policy Table	12-2
13-1	Record Keeping and Policy Checkpoints	13-1
20-1	Predefined Media Profiles	20-2
24-1	Example of Time Slot Definitions	24-3
33-1	QoS Values in Traffic Profile	33-19

1

The Oracle Communications Configuration Management Platform Server

This chapter provides an overview of the Oracle Communications Policy Management Configuration Management Platform (CMP), which includes a policy wizard to aid in creating policies and manageable objects to which policies can refer.

Configuration Management Platform Server

The Configuration Management Platform (CMP) server provides centralized management and administration of policy rules, Policy Management devices, associated applications, and manageable objects, all from a single management console. This browser-based management console supports the following features and functions:

- Configuration and management of MPE devices
- Configuration and management of MRA devices
- Configuration and management of Mediation devices
- Configuration of connections to subscriber profile repository (SPR) servers, including Oracle Communications User Data Repository (UDR) and Oracle Communications Enhanced Subscriber Profile Repository (ESPR) systems
- Definition of network elements
- Management and deployment of policy rules
- Management of objects that can be included in policy rules
- Monitoring of individual product subsystem status
- Administration and management of CMP users
- Upgrading the software on Policy Management devices

Specifications for Using the CMP Server

You interact with the CMP server through a browser-based graphical user interface (GUI). To use the GUI, Oracle recommends the following:

Web Browsers for Wireless and Cable modes

- Mozilla Firefox® release 31.0 or later
- Google Chrome version 40.0 or later

Web Browsers for Wireless and Cable modes

- Mozilla Firefox® release 31.0 or later
- Google Chrome version 40.0 or later

Monitor

- Resolution of 1024 x 768 or greater

Logging In

The CMP system supports either HTTP or HTTPS access. Access is controlled by a standard username/password login scheme.

**Note:**

The CMP system also supports carrier-specific network authentication and authorization environments (SANE Authentication and Radius Authentication and Accounting). For information on setting up an alternate login process, see the *CMP User Guide*.

Before logging in, you need to know the following:

- The IP address of the CMP system
- Your assigned username
- The account password

**Note:**

The profile `admin` has full access privileges and is the assumed profile used in all procedures described in this document. You cannot delete this user profile.

To log in:

1. Open a Web browser and enter the IP address of the CMP system.

The login page opens.

**Note:**

The title and text on the login page are configurable. See the appropriate *CMP User's Guide* for details.

2. Enter your **Username**.
3. Enter your **Password**.
4. Click **Login**.


The main page opens.

You are logged in.

CMP Interface Overview

You interact with the CMP system through an intuitive and highly portable graphical user interface (GUI) supporting industry-standard Web technologies (for example, SSL, HTTP, HTTPS, IPv4, IPv6, and XML). [Figure 1-1](#) shows the structure of the CMP interface.

Figure 1-1 Structure of the CMP Interface



Navigation Pane

Provides access to the various available options configured within the CMP system. You can bookmark options in the Navigation pane by right-clicking the option and selecting **Add to Favorite**. Bookmarked options can be accessed from the **My Favorites** folder at the top of the Navigation pane. Within the My Favorites folder, you can arrange or delete options by right-clicking the option and selecting **Move Up**, **Move Down**, or **Delete from Favorite**. You can collapse the navigation pane to make more room by clicking the button in the top right corner of the pane. Click the button again to expand the pane.

Content Tree

Contains an expandable/collapsible listing of all the defined items for a given selection. For content trees that contain a group labeled **ALL**, you can create customized groups that display on the tree.



Note:

The content tree section is not visible with all navigation selections.

You can collapse the content tree to make more room by clicking the button in the top right corner of the pane. Click the button again to expand the tree. You can also resize the content tree relative to the work area.

Work Area

Contains information that relates to choices in both the navigation pane and the content tree. This is the area in which you perform all work.

Alarm Indicators

Provides visual indicators that show the number of active alarms.

CMP Mode Indicator

If you are in a tiered CMP system, this area indicates if you are on a Network Configuration Management Platform (NW-CMP) or a System Configuration Management Platform (S-CMP) server.

CMP Icons

The CMP interface provides the following icons to perform actions or indicate status:

**Add**

Use this icon to add an item to a list.

**Calendar**

Use this icon to select a date and, in some cases, a time.

**Clone**

Use this icon to duplicate a selection in a list.

**Critical error**

Displays in reports to indicate a critical error during the server replication process.

**or × Delete**

When visible in the work area, selecting the Delete icon deletes an item, removing it from the device.

**Note:**

Deleting an item from the **ALL** folder also deletes the item from any associated group. A delete verification window opens when this icon is selected.

**Details**

This binoculars icon displays when there is more details for an item.

**Edit**

Use this icon to modify a selection in a list.

**External Connection**

When visible in the work area, indicates which server currently has the external connection (the active server).

**Gear**

Displays when a policy references another policy or policy group.

**Hide**

When visible in the work area, selecting this icon removes the item from the current view but does not delete the item.

**Note:**

The item is only hidden during the current session. The item will be visible the next time a user logs into the CMP server.

 Manual

Displays when a field is configured by the user. Hover over this icon to see the name of the device.

 Major error

Displays in reports to indicate a major error during the server replication process.

 Minor error

Displays in reports to indicate a minor error during the server replication process.

 or **Up/Down**

These arrow icons are displayed when you can change the sequential order of items in a list.

 Left/Right

These arrow icons are displayed when it is possible to move an item from one list to another.

**OK status**

Displays in reports to indicate a that the blade replication process completed without error.

 Remove

Removes an item from the group. The item is still listed in the **ALL** group and any other group that has an association with the item. For example, if you remove the device PS_1 from group PS_Group2, PS_1 still displays in the **ALL** group.

 Selection

This icon occurs in the Policy Wizard. The icon is used to select conditions and actions to add to a policy rule.

 Synch broken

When visible in the Upgrade Manager, indicates that the CMP server does not have current information on a server.

 Template

Displays when a field is configured by template. Hover over this icon to see the name of the template. Click the icon to view the template.

**Virtual Machine**

Displays when a Policy Management application is running on a virtual machine (VM).

**View Cart**

Displays the list of configurable objects selected for the **Export** action.

Shortcut Selection Keys

The CMP interface supports the following standard browser techniques for selecting multiple items from a list:

Shift + click

Selects two or more consecutive items. To select consecutive items, select the first item, then press Shift and click the last item to select both items and all items in between.

Control + click

Selects two or more non-consecutive items. To select multiple non-consecutive items, press the Ctrl key as you click each item.

Changing a Password

The Change Password option lets users change their password. This system administration function is available to all users.

**Note:**

The `admin` user can change the password for any user.

If the system administrator has configured your account for password expiration, you will receive a warning when you log in that you must change your password.

**Note:**

To reset the administrator password, contact [My Oracle Support](#).

To change a password:

1. From the **System Administration** section of the navigation pane, select **Change Password**.

The Account Management page opens. If your account is set up with a password expiration period, the expiration date is displayed.

2. Enter your **Current Password**.
3. Enter your **New Password**.

The password is case sensitive. Depending on your system settings, the password must meet the following requirements:

- Cannot contain the username.
- Must contain the minimum number of characters (default is six).
- Must contain characters as specified from the following categories:
 - Must contain at least the specified number of lower case letters.
 - Must contain at least the specified number of upper case letters.
 - Must contain at least the specified number of numbers.
 - Must contain at least the specified number of symbols.

 Note:

Consult with your system administrator to obtain the password criteria for your system.

4. Re-enter your new password to **Confirm Password**.

 Note:

If your new password does not conform to the password strength rules configured for your system, a validation error message appears that includes valid password criteria. Enter and confirm another password that conforms to the criteria.

5. Click **Change Password**.

Your password is changed.

Part I

Using the Policy Wizard

Part I describes how to create and manage policies using the Oracle Communications Policy Management Policy Wizard and lists the rule elements available for your use while creating policy rules.

2

Managing Policy Rules

Policy rules are created and saved within the CMP database and then deployed to MPE devices. The CMP system lets you create and modify the details within policy rules and edit the order in which policy rules are applied to a protocol message.

This chapter describes how to create and manage policy rules. For a list of all conditions, actions, and variables available for use in policies, see:

- [Conditions for Writing Policy Rules](#)
- [Actions for Writing Policy Rules](#)
- [Policy Rule Variables](#)

3

Creating a Policy Rule

Policy rules are created and modified using the policy wizard in the CMP system. After the rule is created or modified, the rule is stored in the policy library. The policy wizard guides you step by step to creating a new policy rule. The wizard displays only the options available at each step.

The following procedure describes how to create a new policy rule, using this wireless policy as an example:

And

```
where the request is creating a new session
where the session is an application session
where the APN matches one of imode.glt2
where the subscriber profile data is not available
```

```
set gg to `op`
```

```
reject message
```

To create a new policy rule:

1. From the **Policy Management** section of the navigation pane, select **Policy Library**.

The content tree displays a list of policy library groups; the default is **ALL**.

2. From the content tree, select the **ALL** group.

The Policy Administration page opens in the work area.

3. Click **Create Policy**.

The Create Policy page opens.

4. Select a starting point for the new policy rule:

- **Blank**

The policy rule is created from the beginning, without any attributes being pre-defined.

- **Use Template**

The policy rule is created based on a user-defined template that can have policy parameters pre-defined. This template can be modified.

- **Copy Existing Policy**

The policy rule is created based on an existing policy rule, which you can modify.

5. Click **Next**.

The Tables page opens.

6. Specify the tables you want to use in the policy. For more details on associating a table with a policy, see [Associating a Policy Table with a Policy Rule](#).

If no tables are associated with the policy rule, click **Next**.

- To specify multiple tables, click the selection icon (●) multiple times
- To move a table so that it is evaluated earlier in the rule, click the up icon (▲)

- To move a table so that it is evaluated later in the rule, click the down icon (▼)
- To delete a table, click  (trash can icon) located to the left of the table.

7. Click **Next**.

The Conditions page opens.

8. Select the policy conditions.

As a condition is selected, it appears in the Description area at the bottom of the page.

You can select multiple conditions, enter multiple instances of each condition, change the order of conditions, group conditions logically, or remove conditions:

- To enter multiple instances of a condition, click the selection icon (●) in the Conditions window multiple times.
- To combine a logical group of conditions, click **And** or **Or**, located in the upper right corner of the Description window, and drag the conditions into the container that appears (represented by a folder icon). You can toggle a container between **And** and **Or** by double-clicking on the folder.
- To change a the evaluation order of a condition or to include the condition within a logical container, drag and drop the condition within the Description area. You cannot drop a container onto itself or one of its sub-containers.
- To negate a condition, change the **is** parameter if present, or click **Not**, located in the upper right corner of the Description area, and drag the condition into the container that appears (represented by a folder icon).
- To delete a condition or container from the rule, select the condition and click **Delete**. A confirmation message displays. Click **OK**.

 Tip:

To add conditions directly to an existing container, select the container first.

Figure 3-1 Example of Selected Policy Conditions

The screenshot shows the 'Create Policy' dialog box. At the top, there is a 'Create Policy' button. Below it, the section 'Conditions: Which condition(s) do you want to check?' contains a list of conditions under the 'User' category. The third condition, 'where the subscriber profile data is available', is selected with a blue radio button. Other conditions include bandwidth limits, expiration timestamps, tier specifications, and user field matches. Below the conditions list is a 'Description (click on an underlined value to edit it):' section. It shows a logical 'And' combination of four conditions: 'where the request is creating a new session', 'where the session is an enforcement session', 'where the APN matches one of imode.q1t2', and 'where the subscriber profile data is not available'. The last condition is highlighted. At the bottom, there is a progress bar with five steps: 'Start', 'Tables', 'Conditions' (which is the current step and has a black dot), 'Actions', and 'Name'. To the right of the progress bar are 'Back', 'Next', and 'Cancel' buttons.

9. Configure parameters information. If a policy condition includes a parameter that requires input, it displays red underlined text in the Description area.
 - a. Click the red underlined text. A window opens, from which you can do one of the following:
 - Select one or more options; for example:

Figure 3-2 Example of Parameter Option Selections

The screenshot shows a small dialog box titled 'Choose the device type:'. It contains a list box with the following options: 'B-RAS', 'Router', 'VOD Server', 'Interface', 'Subscriber Group', and 'Wireline Gateway'. The 'B-RAS' option is currently selected and highlighted in blue. At the bottom of the dialog box are 'OK' and 'Cancel' buttons.

- Enter a value (such as a traffic bit rate or percentage) for example:

Figure 3-3 Example of Parameter Value Entry

- b. Click **OK**.

The popup window closes and the input is added to the policy condition.

10. Click **Next**.

The Actions page opens.

11. Select the required action and any optional actions that the MPE device should execute if the policy request matches the defined conditions of the policy rule.

For example:

Figure 3-4 Example of Selected Policy Actions

- To enter multiple instances of an action, click the selection icon (●) multiple times
- To move an action so that it is evaluated earlier in the rule, click the up icon (▲)
- To move an action so that it is evaluated later in the rule, click the down icon (▼)
- To delete an action from the rule, click 🗑️ (trash can icon) located to the left of the action.

12. Click **Next**.

The Name page opens.

13. Assign a unique name (uniqueness is not case sensitive) to the new policy rule.

 Note:

The name can be up to 255 characters long and cannot contain the following characters: < > \ ; & ' " =

14. Click **Include in Analytics** to generate an analytics data stream for the policy.

See the *Analytics Data Stream Reference* for more information on the Oracle Communications Policy Management Analytics product.

15. Click **Finish**.

The Create Policy page closes.

The policy rule is saved to the policy library in the CMP database.

After a policy rule is created, you must deploy it to MPE devices so it can take effect.

Reference policy rules (rules called by parent policy rules) do not need to be deployed because they are deployed automatically when called by a parent rule. See [Using Reference Policies](#).

4

Parameters Within Policy Rules


When you are defining policy rules, both the conditions and actions may contain parameters. Parameters let you customize the specific situation in which a policy rule will be applied. Some conditions and actions may contain multiple parameters. For example, one possible condition is as follows:

where the device will be handling *greater than 100 upstream reserved* flows

This condition contains four different parameters. The policy wizard displays the parameters using a red font. In this example, *greater than* is a single parameter, as is *100*, *upstream*, and *reserved*.

You can click any parameter to open a pop-up window that lets you specify the value of that parameter. Each parameter has a data type associated with it that determines the values that can be specified: some may be numbers, some may be free-form text, and some may be limited to specific sets of values. For example, the following parameter is limited to a set of text values:

Figure 4-1 Example of a Parameter Pop-up



If you have many policies with similar structures, you can consolidate them using policy tables that capture the differences. For more information on table-driven policies see [Managing Policy Tables](#). To specify a parameter in a rule that uses a policy table, instead of selecting a value click **Use Policy Table** and then select the table column (field) representing the parameter.

QoS Values for Policy Conditions and Actions

[Table 4-1](#) lists the bandwidth values available when defining policy conditions. [Table 4-2](#) lists the bandwidth values available when defining a policy actions.

Table 4-1 QoS values for Policy Conditions

Policy Conditions Type Param Name	Maximum-Requested - Bandwidth -UL	Maximum-Requested - Bandwidth -DL	Guaranteed-Bitrate-DL	Guaranteed-Bitrate-UL	Max-Bitrate-UL	Max-Bitrate-DL
Diameter PCC Rule	$(2^{32} - 1) * 1000$	$(2^{32} - 1) * 1000$	$(2^{32} - 1) * 1000$	$(2^{32} - 1) * 1000$	N/A	N/A
Diameter Bearer	$(2^{32} - 1) * 1000$	$(2^{32} - 1) * 1000$	$(2^{32} - 1) * 1000$	$(2^{32} - 1) * 1000$	N/A	N/A
Diameter APN-Aggregate	N/A	N/A	N/A	N/A	$(2^{32} - 1) * 1000$	$(2^{32} - 1) * 1000$

Table 4-2 QoS values for Policy Actions

Policy Actions Type	Max-Bitrate-UL	Max-Bitrate-DL
Diameter APN-Aggregate	$(2^{32} - 1) * 1000$	$(2^{32} - 1) * 1000$

5

Modifying and Deleting a Policy Rule

Policy rules can be modified and then redeployed to MPE devices. When a policy rule that resides in multiple policy groups is modified, the changes are propagated to the various groups.

Modifying a Policy Rule

To modify a policy rule:

1. From the **Policy Management** section of the navigation pane, select **Policy Library**.
The content tree displays a list of policy library groups; the initial group is **ALL**.
2. From the content tree, select the **ALL** group.
The Policy Administration page opens in the work area, listing the available policies.
3. Select the policy rule you want to modify.
The Policy Administration page displays information about the policy rule.
4. Click **Modify**.
The policy wizard opens in a **Modify Policy** tab.
5. Edit the policy rule information.
See [Creating a Policy Rule](#) for details on the fields within the policy wizard.
6. Click **Finish**.

The policy rule is modified. The modified policy rule is now ready to be added to a policy group (see [Adding a Policy or a Policy Group to a Policy Group](#)) or deployed (see [Deploying a Policy](#)).



Note:

Redeployment of a policy rule is automatically performed to those MPE devices where the policy rule was initially deployed.

Deleting a Policy Rule

Policy rules, including policy rules within a policy group, can be removed from an MPE device when they are no longer needed. Because the policy rule still resides in the CMP database, it can be redeployed at a later date if needed. If a policy rule is no longer needed, it can be deleted from the CMP database.



Note:

Deleting a policy rule from the CMP database automatically removes the policy rule from all associated MPE devices.

To delete a policy rule:

1. From the **Policy Management** section of the navigation pane, select **Policy Library**.

The content tree displays a list of policy library groups; the initial group is **ALL**.

2. From the content tree, select the **ALL** group.

The Policy Administration page opens in the work area, displaying the list of defined policies.

3. Delete the policy rule using one of the following methods:

- From the work area, click  (trash can icon), located to the right of the policy rule.
- From the content tree, select the policy rule and click **Delete**.

A confirmation message appears.

4. Click **OK**.

The policy rule is deleted.

To remove a policy rule from an MPE device, see [Removing a Policy from an MPE Device](#).

6

About Policies

Policies dynamically control how an MPE device processes protocol messages as they pass through it. Using these rules, you can define how and when network resources are utilized by subscribers. For example, when the MPE device receives a request to establish a session with a certain quality of service (QoS) level, you can use a policy rule to approve the request as is, to reject the request, or to make changes in the request before it is forwarded to the intended destination as a network element.

This chapter describes how policies are structured and used within the CMP system. To create policy rules or groups, see [Managing Policy Rules](#) or [Managing Policy Groups](#), respectively.

Before reading this chapter, you should have a basic understanding of the CMP interface. For a discussion of the CMP interface and the terminology used to describe it, see [CMP Interface Overview](#).

Understanding Policy Rules

A policy rule is an **If-Then** statement that has a set of conditions and actions. If the conditions are met, the actions are performed. You create policy rules within the CMP system, using a policy wizard that organizes a large number of conditions and actions to assist you in the construction of policy rules. After you create policy rules, you manually deploy the rules to MPE devices.

You can combine policy rules to provide additional power and flexibility. When there are multiple policy rules, the order in which the policy rules are evaluated can also influence MPE device activity, so the order of evaluation is also configurable through the CMP system. You can also organize policy rules into groups to simplify the management of policy rules. You can cause groups of rules to be executed.

The following are sample scenarios for which you might use policy rules:

- You can modify the contents of protocol messages using policy rules. For example, you could use a policy rule to override the requested bandwidth parameters in a request.
- You can create policy rules that track the use of resources for devices in the network and implement limits on how those resources are used. For example, some cable modems have limits on the number of dynamic flows that they can support. Using policy rules, you can ensure that a cable modem does not exceed this limit.
- Some protocols allow for the provisioning of default Quality of Service (QoS) parameters for subscribers. With these protocols, policy rules can implement subscriber tiers where different subscribers have different bandwidth available.
- You can configure policy rules to monitor the reservation of bandwidth on network elements and notify operators when an element exceeds certain threshold levels.
- In many protocols, the policy server acts as an intermediary between the Application Managers and the QoS enforcement devices. Many of these QoS enforcement devices implement proprietary features that are activated through the use of standard (or non-standard) fields in protocol messages. Using policy rules, you can activate these

proprietary features on behalf of the Application Managers, thus allowing them to use these features without modification.

About Creating and Using Policies

To create and use policies you must:

1. Create manageable objects – see [About Creating Manageable Objects](#).
2. Create and manage policy rules that use the objects – see [Creating a Policy Rule](#).
3. Deploy the policy rules – see [Deploying Policies](#).

Structure and Evaluation of Policy Rules

The following topics provide an overview of how policy rules are structured and evaluated.



Note:

The conditions, actions, and parameters available for your use in creating policy rules depend on the mode in which the CMP system is operating.

Structure of Policy Rules

Understanding how a policy rule is structured is helpful in understanding other Policy Management concepts. A policy rule is defined in an if-then structure, consisting of a set of conditions that the MPE device compares to information extracted from protocol messages or obtained from subscriber records, and a set of actions that are executed (or not executed) when the conditions match. Many conditions can be tested for existence or non-existence (by optionally selecting the logical operator **NOT** or using, where available, the policy condition operator **is** or **is not**).

Policy Parameters

When you define a policy rule, you select from a list of available conditions and actions. Most of the conditions and actions have parameters (that is, they contain placeholders that may be replaced with specific values to allow you to customize them as needed).

For example, consider the following policy rule, which has one condition and two actions:

```
where the device will be handling greater than 100 upstream reserved
flows
```

```
apply profile Default Downstream Profile to request
continue processing message
```

The condition, **where the device will be handling...**, allows the following parameters to be specified:

- An operator (*greater than*)

- A value (*100*)
- The flow direction (*upstream*)
- The bandwidth reservation type (*reserved*)

The first action, **apply profile...**, specifies a single parameter that is the name of a traffic profile to be applied to the request. The second action, **continue processing message**, instructs the MPE device to evaluate the remaining rules within the policy rules list (as opposed to immediately accepting or rejecting the request). The conditions and actions that are available for writing policies are discussed later in this section.

Policy Logical Operators

The policy wizard supports creation of rules using an explicit **AND** logical operator that contains a set of conditions. An AND operator must include at least two conditions. The actions are taken if all conditions are evaluated as true. For example, you can use an AND operator to define two conditions as follows:

```
And
  where the request is re-authorizing an existing session
  where the enforcement session is a DPI enforcement session
  .
  .
  .
```

The policy wizard supports creation of rules using an **OR** logical operator that contains a set of conditions. An OR operator must include at least two conditions. The actions are taken if any condition is evaluated as true. For example, you can define the following set of conditions using an OR operator:

```
Or
  where the request is creating a new session
  where the session is an enforcement session
  where the APN matches one of imode.glt2
  where the subscriber profile data is not available
  .
  .
  .
```

The policy wizard supports creation of rules using a **NOT** logical operator that contains a single condition. The actions are taken if the condition is evaluated as false. For example, you can define the following using a NOT operator:

```
Not
  where today is a weekend day using CONFIGURED LOCAL TIME
  .
  .
  .
```

**Note:**

Many conditions also include optional **is** and **is not** parameters. These parameters are functionally equivalent to (that is, synonymous with) using the **NOT** operator, and you are free to use or mix **NOT** with **is** and **is not** as you prefer.

Finally, the policy wizard supports creation of rules using combinations of logical operators. You can nest operators. For example, you can define the following rule:

```
Or
  And
    Not
      where the service info status is one of
        FINAL_SERVICE_INFORMATION
    where the session is an enforcement session
  where the session is an application session
Not
  where the session is an application session

evaluate policy 5555
reject message
```

The policy wizard validates condition trees.

Parent and Reference Policies

As a result of evaluating conditions, a policy can execute another policy. A policy that calls another policy is called a parent policy, and a policy executed by another policy is called a reference policy. A policy can be both a parent policy and a reference policy. Additionally, you can group policies, and a parent policy can execute all the policies in the group.

**Note:**

Do not nest policies more than five levels deep.

Evaluating Policy Rules

To write policy rules, it is important to understand how they are evaluated by the Policy Rules Engine contained within the MPE device, and how the engine fits into the protocol message processing within the MPE device.

If you look at the policy conditions that are available, you will see that many are not protocol specific. Although you can write protocol-specific policy rules, the Policy Rules Engine does not have any protocol knowledge. Instead, it deals with a set of abstractions that are mapped to the underlying protocol messages that are being processed. This allows the same policy rules to be used across multiple protocols.

When the MPE device receives a protocol message, it performs the initial processing of that message and then determines whether or not the message should be processed by the Policy Rules Engine. Generally, protocol messages that are either requesting bandwidth or modifying previous requests for bandwidth are processed by the Policy Rules Engine. Most other protocol messages are not. For example, a protocol message that releases bandwidth is typically not processed by the Policy Rules Engine because there is no reason to prevent or modify that action.

After a message is identified as a candidate for the policy rules, the MPE device attempts to associate as much information with the request as possible. For example:

- Which network elements will be impacted if the request is allowed to proceed?
- Which subscriber is associated with the request? What services is that subscriber entitled to?
- Which application is associated with the message?
- What time zone is the user equipment located in?

The reason for collecting this information is to make it available to the policy rules. The information that can be associated varies and depends on a number of factors, including:

- The protocol in question and how much information is provided in the protocol message
- The amount of network topology information that has been provisioned into the MPE device
- Whether there are other protocol sessions that can be associated with this message
- Whether there are external data sources configured that the MPE device can use to associate information with the message

When the process of associating information with the request is complete, the MPE device analyzes the information and maps it into several important abstractions that are central to the functioning of the Policy Rules Engine:

1. A list of network devices that the request affects. A network device is any network element, any logical or physical sub-component of a network element, or any other network equipment.
2. A list of flows associated with the request. A flow is a logical grouping of one or more packet filters and associated information such as QoS, charging, or service information. A flow can be in a single direction (either upstream or downstream). A flow can be a collection of bandwidth parameters. Different protocols can have a different number of flows associated with a message.

For example:

- In Cable mode, the PCMM messages have only one flow per request.
 - In Wireless mode, the DQoS messages have one or two flows per request (for each direction).
3. A list of policies associated with the request. This includes policy groups and reference policies called by the parent policy.

After constructing these lists, the Policy Rules Engine applies the policy rules according to the following algorithm:

For each network device:

 For each flow that is being created or modified:

 For each policy that is being evaluated:

```

        Evaluate all policy rules
      End
    End
  End

```

A device refers to any device that creates a Gx session, such as a PGW or GGSN; the enforcement device associated with the corresponding Gx IP-CAN session; or any device that creates a Gxx session, such as an HSGW.

It should be clear from this algorithm that a single message can result in multiple policies being evaluated, and a policy rule being evaluated multiple times. This is important to understand to ensure that the policy rules you write operate in the way you intended.

By using parent policies, reference policies, and policy groups, you can control the order of policy execution. For example, assume there are four policies: two parent policies, *policy1* and *policy4*, and two reference policies, *policy2* and *policy3* that are in a policy group, *group1*. The hierarchy is as follows:

```

policy1
  policy2
  policy3
policy4

```

The order of execution can vary, depending on how each policy evaluates and what actions each contains:

- The normal order of execution would be *policy1*, *policy2*, *policy3*, *policy4*.
- If the conditions in *policy1* evaluate to false, the order of execution would be *policy1*, *policy4*.
- if *policy2* includes the mandatory action *break from policy level*, the order of execution would be *policy1*, *policy2*, *policy4*.

If the optional 3GPP-MS-TimeZone AVP is available over the Gx protocol from a PCEF, the MPE device can compute the local time for user equipment, even if the user enters a different time zone or the time offset changes because of Daylight Saving Time.



Note:

Policies created using a more recent version of the CMP software may not evaluate and execute as intended on an MPE device running an older version of the MPE software. To ensure that policies are evaluated and executed as intended, update all systems to the same version of the software.

Activating and Deactivating Policy Rules

Rules can be activated and deactivated at specific times by selecting actions that are time-based. The methods by which activation/deactivation times can be defined are:

Time Period

Uses pre-defined time period. At least one time period must be defined to use this option.

Policy Table field

Uses time-related field from a policy table. At least one policy table must be defined, at least one time-related field must be specified in that table, and that table must be selected during the rule definition process to use this option.

Absolute time

Uses exact time, or a combination of the time and date, to define rule activation/deactivation. If only a time is specified, the begin/end dates are calculated as the minimum future dates for those times.

Relative time

Uses the number of hours, minutes, or seconds from the current time to start/end. For example, the value 5 with units of hours would state that a rule should activate (or deactivate) 5 hours after this policy condition is processed by the MPE device. Expressions may include policy variables.

**Note:**

If an activation time is not specified, a rule becomes active immediately. If a deactivation time is not specified (or it is in the past), a rule never deactivates.

**Caution:**

If all rules defined in a system have a deactivation time specified, all rules for the session on a PCEF can become deactivated. To prevent this from occurring, the session on the PCEF is set to validated 1 to 30 minutes before the last active rule deactivates.

Using Reference Policies

Multiple policies that share the same conditions can be simplified by including the common conditions in a parent policy and any unique conditions in reference policies. During execution, the common conditions are only evaluated once.

For example, consider the following policies, which apply tiers to session requests. Each policy uses the same conditions, and the Policy Rules Engine evaluates the same conditions up to three times:

Bronze Policy

```
where the request is creating a new session
  and where the flow is an application flow
  and where the AF-Application-ID matches one of voip
  and where the tier is one of Bronze
```



```
apply bronze to request
accept message
```

Silver Policy

```
where the request is creating a new session
  and where the flow is an application flow
  and where the AF-Application-ID matches one of voip
  and where the tier is one of Silver
apply silver to request
accept message
```

Gold Policy

```
where the request is creating a new session
  and where the flow is an application flow
  and where the AF-Application-ID matches one of voip
  and where the tier is one of Gold
apply gold to request
accept message
```

The same results can be obtained using a parent policy and the reference policies Bronze Policy, Silver Policy, and Gold Policy contained in a policy group named Tier Policies:

```
where the request is creating a new session
  and where the flow is an application flow
  and where the AF-Application-ID matches one of voip
evaluate policy group Tier Policies
```

Bronze Policy

```
where the tier is one of Bronze
apply bronze to request
accept message
```

Silver Policy

```
where the tier is one of Silver
apply silver to request
accept message
```

Gold Policy

```
where the tier is one of Gold
apply gold to request
accept message
```

Modes and the Policy Wizard

The policy wizard varies depending on the mode in which your CMP system is running. The mode configuration affects the following:

- Entire categories of conditions are made available or unavailable.
- Specific conditions and/or actions are made available or unavailable.
- Some conditions have a slightly different phrasing.
- The available values for some parameters vary.

If your policy wizard does not include a category, condition, action, or value documented here, it means that those categories, conditions, or actions are not available in your present CMP mode.

Deploying Policies

This chapter describes how policies are deployed from the CMP database to MPE devices.

About Deploying Policies

Deploying a policy is the act of transferring the policy from the CMP database to an MPE device. After a policy is deployed, the rules defined within the policy are used as decision-making criteria by the MPE device.

Figure 7-1 shows how policies P1 through P7 are created in the CMP database and then deployed individually to different MPE devices within the network. Each of the policies is associated individually with the MPE device to which it is deployed. In the example, each policy server (MPE device) displays the policies that have been deployed to it and the order in which they are applied to policy requests, from top to bottom.

Figure 7-1 Policy Deployment





Figure 7-2 shows how the same library of policies can be grouped first and then deployed as policy groups. When a policy group is created, the policies are arranged in the order in which they are to be evaluated. Grouping policies makes deployment of multiple policies easier and helps to ensure consistency in how policies are applied to policy requests on different MPE devices.


Figure 7-2 Policy Group Deployment



When you first create a policy rule, that rule exists only within the CMP database. After the policy rule is deployed, the policy rule is automatically redeployed when you make any changes. Automatic redeployment also applies to policy groups: any change to a policy group triggers automatic redeployment. If a policy group is deployed to one or more MPE devices and you add a new policy rule to the policy group, the rule is automatically deployed to those MPE devices.

Figure 7-3 shows that when a policy (P3) is modified, its associated groups (PG-1 and PG-3) are redeployed automatically.

Figure 7-3 Policy Redeployment




You do not need to deploy policy rules that are referenced by other deployed policy rules or policy groups. Reference policies are automatically deployed when called by the parent policy.

Deploying a Policy

To deploy a policy:

1. From the **Policy Management** section of the navigation pane, select **Policy Library**.
The content tree displays a list of policy library groups; the initial group is **ALL**.
2. From the content tree, select the policy rule or policy group you want to deploy.
The Policy Administration page opens in the work area, displaying either the policy rule details or the list of the policy rules and policy groups contained in the selected policy group.
3. Click **Deploy**.
The policy server tree is displayed, listing all possible target MPE devices and server groups. You can expand the tree view if necessary.
4. Select the target MPE devices or policy server groups.

Figure 7-4 Policy Server Selection Window



An icon indicates whether you have selected some (📌) or all (📌) MPE devices to which to deploy the policy.

5. Click **Deploy**.

A confirmation message appears followed by a list of MPE devices to which the policy was deployed.

The policy information is saved to each selected MPE device.

Changing the Sequence of Deployed Policies on an MPE Device

To change the sequential order of policies:

1. From the **Policy Server** section of the navigation pane, select **Configuration**.

The content tree displays a list of policy server groups; the initial group is **ALL**.

2. From the content tree, select the MPE device.

The Policy Server Administration page opens in the work area, displaying information about the MPE device.

3. Select the **Policies** tab.

4. Click **Modify**.

The Manage Policies page opens in the work area.

5. Use any of the following options to change the sequential positioning of the policies:

- Use the 📌 (top) and 📌 (bottom) icons, located to the left of policy rules or policy groups. The 📌 (top) icon moves the item it to the top of the list. The 📌 (bottom) icon moves the item it to the bottom of the list.
- Drag and drop policy rules or policy groups to a different position in the sequence.

- Change the sequence numbers, located to the left of policy rules or policy groups. Click **Update Order** to refresh the display.
- Optionally, you can click **Undo** or **Redo** to step back and forth through your changes.

6. Click **Save**.

The sequence of policies is changed on the MPE device. A confirmation message appears in the work area.

Removing a Policy from an MPE Device

To remove a policy from an MPE device:

1. From the **Policy Server** section of the navigation pane, select **Configuration**.

The content tree displays a list of policy server groups; the initial group is **ALL**.

2. From the content tree, select the MPE device from which you want to remove the policy rule or policy group.

The Policy Server Administration page opens in the work area, displaying information about the MPE device.

3. Select the **Policies** tab.

4. Click **Modify**.

The Manage Policies page opens.

5. Click (scissors icon) located to the right of the policy rule or policy group that you want to remove.

The policy is removed from the list.

6. Repeat step 5 as required.

7. Click **Save**.

A confirmation message appears.

The policy is removed from the MPE device.

8

Managing the Policy Library

This chapter describes how to manage your policy library and how to control which policies are deployed and in what order.

Displaying a Policy

To display a policy:

1. From the **Policy Management** section of the navigation pane, select **Policy Library**.


The content tree displays a list of policy library groups; the initial group is **ALL**.

If a policy is a parent policy, a gear icon (⚙️) appears next to the policy name in the content tree.

2. From the content tree, select the policy to display.

The Policy Administration page opens in the work area, displaying the policy. [Figure 8-1](#) shows an example.

Figure 8-1 Sample Policy Description



You can choose from two logical views of policy conditions:

- A tree format (shown)
- A Boolean expression format similar to SQL

To switch between views, click **Toggle View**.

If the policy evaluates a policy group, the policies in the group are displayed. Click a policy name to see details of that policy. If a policy in the group is a parent policy, the parent policy's referenced policies are also displayed.

Organizing Policies

The CMP system includes features to simplify the management of multiple policies.

The order in which policies are evaluated is important. The CMP system lets you configure the evaluation order of policies. See [Structure and Evaluation of Policy Rules](#).

The CMP system provides a policy template feature to simplify the creation of multiple policy rules that have similar conditions and actions. After you create a policy template, you can use it to create additional rules. See [Creating a Policy Template](#).

The CMP system also provides a policy rule grouping feature. Policy rules can be organized into groups and the groups can be used to simplify the process of deploying policies to MPE devices. See [Creating a Policy Group](#). Policy rule groups can be executed with a single action. See [Structure and Evaluation of Policy Rules](#).

Policies with similar conditions or actions can be consolidated into tabular form. See [Managing Policy Tables](#).

Importing and Exporting Policies, Policy Groups, and Templates

Policies, policy groups, and templates can be exported from the CMP database for inspection or backup purposes. For more information about importing and exporting, see the *CMP User's Guide*.

9

Managing Policy Tables

This chapter describes how to create, modify, delete, and view policy tables, which are independent objects that you can use to capture differences in policy structures.

You can manage multiple policies with small differences by abstracting the differences into tables. The process of modifying the policies, or creating new, similar policies, then becomes a matter of modifying the policy table, which is simpler and less prone to error.

About Policy Tables

In practical use, many policies are very similar, having only small differences between them. Policy tables are an available option in the policy wizard. A policy table abstracts the differences between related policies.

Using a policy table instead of creating many similar policies makes the tasks of adding new policies, modifying existing sets of policies, and checking consistency among related policies simpler and less prone to error.

Policy tables resemble database tables and contain the following elements:

- Table name
- Table description
- Column definitions
Every column has a definition that contains a name, data type, and indication if the column is a key column. Every entry in the column must have the same data type. Every table must have a key column. Any data associated with a message, including fields (such as a quota or RAT type) and sub-fields (such as a user account ID or tier name), can be used as a key.
- Policy variable (for key columns only)
These are used to obtain the value from the policy context when using the policy table to look up a row.
- Data
The contents of the table cells. (Blank cells are not allowed in a policy table.)


Each row in a policy table can be thought of as a scenario, and each row can replace a policy. Substitutions in policy condition and action parameters can include the values in a specified policy table.

[Table 9-1](#) shows an example of a simple policy table. The first column lists one or more access point names (APNs) and is the key column. The second column contains a PCC rule that will be installed as part of the execution of a policy. The third column contains one or more PCC rules that will be removed as part of the execution of a policy. The second and third columns must contain names of PCC rules defined as traffic profiles in the CMP database.

Table 9-1 Example of a Policy Table

APN	Install	Remove
apn1.com	pcc_rule_1	pcc_default_1, pcc_basic
apn2.com	pcc_rule_2	pcc_default_2, pcc_basic
apn3.com, apn4.com	pcc_rule_1	pcc_default_1
apn5.com, apn6.com	pcc_rule_2	pcc_default_2

Figure 9-1 shows how to define the key column for this example in the policy wizard using the variable `Request.CalledStationId`.

Figure 9-1 Defining a Policy Table Key Column

Each policy can have zero or more policy tables. To support the use of multiple policy tables, policies refer to a policy table using an alias. Each policy can use a different alias for the same policy table. For example, a policy named PCC rules to install and remove based on APN can be referred to in a policy as `pccrules`. Policies can use table cells addressed as `table_name.column_name`.

The following policy rule uses the defined policy table. The italicized text represent substitutions. The table references begin with `pccrules`.

```
use table 'PCC rules to install and remove based on APN' called
'pccrules'
where the request is modifying an existing session
      and where the session is a credit control session
      and where the requested quota is one of Bucket
Exceeded, OS_no_TV_volume
      and where the quota usage reporting reason is one of validity
time expired
      and where the user Custom1 matches one of 101
install pccrules.install PCC rules for flow
remove pccrules.remove PCC rules
send notification to syslog with `100;{User.MSISDN};{User.AccountId};
{User.IMSI};{Session.IMEI};{Date} {Time}; Info GalacTel : You have a
new 500 minutes to enjoy your mobile Internet offer. Beyond that the
flow will be reduced.; {Date} {Time};{Date} {Time};{User.Custom1};
{User.BillingDay}` and severity 'Emergency'

accept message
```

The use of policy tables is not required. The decision to use a policy table may arise after you have created a series of production policy rules, if you notice that the policies differ only in a few small ways.

You can also use virtual policy tables to test policy table changes before you deploy the changes on the network. Policy tables that are used by virtual policy tables are subject to additional validations. For information about validations for policy tables used by a virtual policy table, see [About Virtual Policy Tables](#).

About Data Matching

When policy tables are evaluated, values in key column cells are evaluated against information parsed out of messages or retrieved from external data sources and stored in the policy context. For example, fields such as entitlements or multivalued custom fields can be retrieved from a subscriber profile stored in a subscriber profile repository (SPR) system. By default, values are evaluated as single entities, and matches must be exact. However, you can optionally specify that values be treated as a set of delimited values and evaluated as multi-value fields and accept as a match a complete or subset match of the values within the key column cell. The first row with a successful match is used. You can define up to 50 values within one cell.

Using multi-value keys makes a policy table more flexible and reduces the number of rows needed.

[Policy Matching Operations](#) shows the available matching operations between policy context data and key column cell values. Data matching is case insensitive.



Note:

If no delimiter is defined, the data in the key column cell is used as is and not parsed.

[Example of Data Matching](#) provides a simple example of data matching and compares the results from each matching operation.

Policy Matching Operations

Wildcard

One or more wildcarded values in the key column cell are compared to the values in the policy context data. If there is any match, the row is matched. The asterisk (*) character represents any number of characters, and the period (.) character represents any single character.

```
child*,student*,family..
```

Policy Context Set Contains All Multiple Valued Key Column

A multi-valued key column cell is compared to multivalued policy context data. If the policy context data is a subset of the key column cell data, the row is matched.

```
gold|silver|bronze
```

Multiple Key Column Set Contains Single Value Context

A multivalued key column cell is compared to single-value policy context data. If the policy context data is a subset of the key column cell data, the row is matched. (The policy context data is evaluated as a string and must be included in the key column cell data.)

weekday|weekend

Multiple Policy Context Set Contains Single Value Key Column

A single-value key column cell is compared to multivalued policy context data. If the key column cell data is a subset of the policy context data, the row is matched. (The key column cell data is evaluated as a string, and must be included in the policy context data.)

gold

Key Column Value Set Contains Any Multiple Valued Context

A multivalued key column cell is compared to multivalued policy context data. If any values within the key column cell data match any values of the policy context data, the row is matched.

ExampleInc,ExampleInc Plus,ExampleInc Premium,ExampleInc
Business

Equivalence

A multivalued key column cell is compared to multivalued policy context data. If the key column cell data matches the policy context data, the row is matched. (The order does not matter.)

Gold!EU

Key Column Set Contains All Multiple Valued Policy Context

A multivalued key column cell is compared to multivalued policy context data. If the key column cell data is a subset of the policy context data, the row is matched.

Gold!EU!Weekend

Matchlist

The policy context data is compared to the match list specified in a key column cell. If the policy context data is a subset of the data contained in the match list, the row is matched. This data matching operation is available when the policy variable ***select-list(s)*** is selected for **Column Type**. The **Column Type** field will be auto-filled as **Token List Name** and the **Matching Operation** field will be auto-filled as **MatchList**. See [Managing Match Lists](#) for more information about match lists.

ent_Match_List1

Example of Data Matching

As an example of how matching operations work, consider a policy table with the following multirow key column:

Data.UserLevel

Gold,Silver

Data.UserLevel

Bronze

Gold,Silver,Bronze

GO*,SILVE.

If the delimiter is turned off (not selected), any matching algorithm will compare the policy context value to the entire key column cell. For example, the first row of the column is evaluated as the string `Gold,Silver` and not as two values. If the policy context has a `UserLevel` of `Bronze`, the second row will match. However, the third row would not match as it would be seen as `Gold,Silver,Bronze` and compared to `Bronze` not an exact match.

Key Column Set Contains All Multiple Valued Policy Context will only return true if the key column cell contains all of the policy context information. For example, if the policy context has a `UserLevel` of `Silver,Bronze`, the first row of the column will not match, but the third row will.

Policy Context Set Contains All Multiple Valued Key Column is the opposite of the previous matching operation: The policy context information must contain all of the key column cell values. For example, if the policy context has a `UserLevel` of `Silver,Bronze`, only the second row of the column will match.

Key Column Value Set Contains Any Multiple Valued Context means that if any values in the key column cell and the policy context information are the same, the match is true. For example, if the policy context has a `UserLevel` of `Silver,Bronze`, every row of the column will match, because each row contains the same information as the Policy Context. (The policy will use the first row matched.)

Equivalence means that all values must be exact. The order does not matter; that is, `Silver,Gold` and `Gold,Silver` are the same. However, all set information must be in both values. For example, if the policy context has a `UserLevel` of `Silver,Bronze` then it does not match any row in the table because the two sets are never exact. However, if the policy context has a `UserLevel` of `Silver,Gold,Bronze`, the third row of the column will match, because the order does not matter. (If the delimiter were turned off, the operation would perform a string comparison of `Silver,Gold,Bronze` with `Gold,Silver,Bronze` which is not a match.)

Multiple Key Column Set Contains Single Value Context will give the same results as **Key Column Set Contains All Multiple Valued Policy Context**. However, the policy context is not separated into delimited values.

Multiple Policy Context Set Contains Single Value Key Column will give the same results as **Policy Context Set Contains All Multiple Valued Key Column**. However, the key column cell values are not separated into delimited values, only the policy context (if possible).

Wildcard is the intersection of the policy context with the key column call values, taking into account wildcards. For example, if the policy context has a `UserLevel` of `Gold` then the first and fourth row of the column will match. The same is true if the policy context has a `UserLevel` of `Silver` instead. However, if the policy context has a `UserLevel` of `GOLDEN` then only the fourth row will match.

Matchlist is not an available data matching operation in this example.

Policy Table Case Study

The following case study is derived and simplified from actual carrier policies and illustrates how a large set of policies can be consolidated using a policy table.

A wireless carrier named Example Inc. offers three monthly data usage plans for its subscribers. The monthly quota levels are 100 MB, 2 GB, and 150 GB. Seven policies are used to capture the business logic for each usage plan, as follows:

- When subscribers near their monthly quota limit, the carrier sends an SMS notification.
- When subscribers reach their monthly quota limit, the carrier sends an SMS notification, sets an additional quota (at an additional price), sets a new warning threshold, and sets a new limit threshold.
- When subscribers reach the additional limit, the carrier sends an SMS notification and throttles additional usage to 64 kbps.

The rules for each usage plan are collected in a policy group: to support the three plans, there are three policy groups. Finally, triggering policies determine which policy group to execute based on the entitlement of the subscriber.

The names the carrier uses for the groups, and the names of the policies each contains, are as follows. The groups are named for the data plans (100_MB, 2_GB, and 100_GB), and the policies are named for the data plans and the actions each policy performs.

Table 9-2 Quotas and Policy Names

Group Name	Policy Name
Quota_100_MB	Quota_100_MB_send_70_percent_SMS
	Quota_100_MB_send_100_percent_SMS
	Quota_100_MB_additional_quota_send_100_percent_SMS
	Quota_100_MB_set_70_percent_volume_threshold
	Quota_100_MB_set_100_percent_volume_threshold
	Quota_100_MB_additional_quota_set_100_percent_volume_threshold
	Throttle_64_kbps_100_MB
Quota_2_GB	Quota_2_GB_send_90_percent_SMS
	Quota_2_GB_send_100_percent_SMS
	Quota_2_GB_additional_quota_send_100_percent_SMS
	Quota_2_GB_set_90_percent_volume_threshold
	Quota_2_GB_set_100_percent_volume_threshold
	Quota_2_GB_additional_quota_set_100_percent_volume_threshold
	Throttle_64_kbps_2_GB
Quota_100_GB	Quota_100_GB_send_90_percent_SMS
	Quota_100_GB_send_100_percent_SMS
	Quota_100_GB_additional_quota_send_100_percent_SMS
	Quota_100_GB_set_90_percent_volume_threshold
	Quota_100_GB_set_100_percent_volume_threshold
	Quota_100_GB_additional_quota_set_100_percent_volume_threshold
	Throttle_64_kbps_100_GB

Comparing the triggering policies shows that they differ only in the name of the entitlement to match and the policy group to execute:

- Trigger Policy: Evaluate 3G Volume Quota Group Quota_100_MB

```
where the ENTITLEMENTS is contained in Match Lists Ent_100MB_Quota
evaluate policy group Quota_100_MB
```

- Trigger Policy: Evaluate 3G Volume Quota Group Quota_2_GB

```
where the ENTITLEMENTS is contained in Match Lists Ent_2GB_Quota
evaluate policy group Quota_2_GB
```

- Trigger Policy: Evaluate 3G Volume Quota Group Quota_100_GB

```
where the ENTITLEMENTS is contained in Match Lists Ent_100GB_Quota
evaluate policy group Quota_100_GB
```

Similarly, comparing the corresponding policies in different groups shows that they are mostly the same, with only a few isolated differences:

- Group: Quota 100MB; Policy: Quota 100MB send 70 percent SMS

```
where the user is using greater than or equal to 70 percent and less than
100 percent of volume for DP_QUOTA.100MB quota
And where the event trigger is one of USAGE_THRESHOLD_REACHED
send SMS `You have consumed 70 % of your total quota allotted on Example
Inc.` to user. Request delivery receipt `default`.
send notification to syslog with `SMS 70%;{User.E164};{User.Custom5};
{User.Custom6};GOLD;{User.Entitlement};You have consumed 70 % of your
total quota allotted on Example Inc.` and severity `Info`
Advanced: set values for QoS and Charging parameters to
Diameter IP-CAN Session Usage Monitoring  USAGE_MONITORING_ENABLED

continue processing message
```

- Group: Quota 2GB; Policy: Quota 2GB send 90 percent SMS

```
where the user is using greater than or equal to 90 percent and less than
100 percent of volume for DP_QUOTA.2GB quota
And where the event trigger is one of USAGE_THRESHOLD_REACHED
send SMS `You have consumed 90 % of your total quota allotted on Example
Inc.` to user. Request delivery receipt `default`.
send notification to syslog with `SMS 90%;{User.E164};{User.Custom5};
{User.Custom6};GOLD;{User.Entitlement};You have consumed 90 % of your
total quota allotted on Example Inc.` and severity `Info`
Advanced: set values for QoS and Charging parameters to
Diameter IP-CAN Session Usage Monitoring  USAGE_MONITORING_ENABLED

continue processing message
```


- **Group: Quota 100GB; Policy: Quota 100GB send 90 percent SMS**

where the user is using *greater than or equal to 90 percent* and
less than 100 percent of volume for *DP_QUOTA.100GB* quota
 And where the event trigger is one of *USAGE_THRESHOLD_REACHED*
 send SMS *`You have consumed 90 % of your total quota allotted on Example Inc.`* to user. Request delivery receipt *`default`*.
 send notification to syslog with *`SMS 90%;{User.E164};{User.Custom5};{User.Custom6};GOLD;{User.Entitlement};You have consumed 90 % of your total quota allotted on Example Inc.`* and
 severity *`Info`*
 Advanced: set values for QoS and Charging parameters to
Diameter IP-CAN Session Usage Monitoring USAGE_MONITORING_ENABLED

continue processing message

- **Group: Quota 100MB; Policy: Quota 100MB additional quota set 100 percent volume threshold**

where the user is using *greater than or equal to 100 percent* of
total volume for *DP_QUOTA.100MB* quota
 And where the user is using *less than 100 percent* of *total volume*
 for *DP_QUOTA_ADDL.3GB* quota
 remove PCC rule types *all* for *all*
 install *16Mbps_DL_5.76Mbps_UL* PCC rules for *flow*
 grant *total volume* to *100 percent* used for *DP_QUOTA_ADDL.3GB*
 Advanced: set values for QoS and Charging parameters to
Diameter Enforcement Session Event Triggers REVALIDATION_TIMEOUT,
USAGE_THRESHOLD_REACHED
Diameter IP-CAN Session Usage Monitoring USAGE_MONITORING_ENABLED

accept message

- **Group: Quota 2GB; Policy: Quota 2GB additional quota set 100 percent volume threshold**

where the user is using *greater than or equal to 100 percent* of
total volume for *DP_QUOTA.2GB* quota
 And where the user is using *less than 100 percent* of *total volume*
 for *DP_QUOTA_ADDL.4GB* quota
 remove PCC rule types *all* for *all*
 install *16Mbps_DL_5.76Mbps_UL* PCC rules for *flow*
 grant *total volume* to *100 percent* used for *DP_QUOTA_ADDL.4GB*
 Advanced: set values for QoS and Charging parameters to
Diameter Enforcement Session Event Triggers REVALIDATION_TIMEOUT,
USAGE_THRESHOLD_REACHED
Diameter IP-CAN Session Usage Monitoring USAGE_MONITORING_ENABLED

accept message

- Group: Quota 100GB; Policy: Quota 100GB additional quota set 100 percent volume threshold

where the user is using *greater than or equal to 100 percent of total volume* for *DP_QUOTA.100GB* quota

And where the user is using *less than 100 percent of total volume* for

DP_QUOTA_ADDL.5GB quota

remove PCC rule types *all* for *all*

install *16Mbps_DL_5.76Mbps_UL* PCC rules for *flow*

grant *total volume* to *100 percent* used for *DP_QUOTA_ADDL.5GB*

Advanced: set values for QoS and Charging parameters to

Diameter Enforcement Session Event Triggers REVALIDATION_TIMEOUT,

USAGE_THRESHOLD_REACHED

Diameter IP-CAN Session Usage Monitoring USAGE_MONITORING_ENABLED

accept message

All the differences in the seven policies for the three groups can be tabulated using only six columns and three rows, as follows. Because of the similarities from group to group, these policies are good candidates for using a policy table. These three groups can be replaced by one set of policies using variables for differences and one policy table with three rows. The table's key column, representing the scenarios, is a policy context property. The table column headings become the names of the other variables used in the policies.

Table 9-3 Differences Between Quotas

Policy Variable Scenario	Base Quota	Additional Quota	Percent Limit	Addition al Limit	Grant Quota
100 MB	DP_QUOTA.100 MB	DP_QUOTA_ADDL.3GB	70	3 GB	DP_QUOTA_ADDL.3GB
2 GB	DP_QUOTA.2GB	DP_QUOTA_ADDL.4GB	90	4 GB	DP_QUOTA_ADDL.4GB
100 GB	DP_QUOTA.100 GB	DP_QUOTA_ADDL.5GB	90	5 GB	DP_QUOTA_ADDL.5GB

The triggering policies are now rewritten to use the policy table and a single policy group, which in this case study is named *QUOTA*. A policy context property is used as the key to locate the row in the table to use.

- Table-Driven Trigger Policy: Evaluate 3G Volume Quota Group 100 MB

where the *ENTITLEMENTS* is contained in Match Lists *Ent_100MB_Quota*
 set policy context property *scenario* to *100MB*
 evaluate policy group *QUOTA*

- Table-Driven Trigger Policy: Evaluate 3G Volume Quota Group 2 GB

where the *ENTITLEMENTS* is contained in Match Lists *Ent_2GB_Quota*
 set policy context property *scenario* to *2GB*
 evaluate policy group *QUOTA*

- Table-Driven Trigger Policy: Evaluate 3G Volume Quota Group 100 GB

```
where the ENTITLEMENTS is contained in Match Lists Ent 100GB Quota
set policy context property scenario to 100GB
evaluate policy group QUOTA
```

The policies in the QUOTA group are now rewritten to use the policy table, which in this case study is named `Quota_table`, and variables. The sample policies shown previously are rewritten as follows:

- Group: QUOTA; Policy: Quota send Warning percent SMS

```
use table Quota_table called table
where the user is using greater than or equal to table.PctLmt percent
and less than 100 percent of volume for table.BaseQuota quota
And where the event trigger is one of USAGE_THRESHOLD_REACHED
send SMS `You have consumed table.PctLmt % of your total quota
allotted on Example Inc.` to user. Request delivery receipt `default`.
send notification to syslog with `SMS table.PctLmt%;{User.E164};
{User.Custom5};{User.Custom6};GOLD;{User.Entitlement};You have
consumed table.PctLmt % of your total quota allotted on Example Inc.`
and severity `Info`
Advanced: set values for QoS and Charging parameters to
Diameter IP-CAN Session Usage Monitoring  USAGE_MONITORING_ENABLED

continue processing message
```

Group: QUOTA; Policy: Quota additional quota set 100 percent volume threshold

```
use table Quota_table called table
where the user is using greater than or equal to 100 percent of total
volume for table.BaseQuota quota
And where the user is using less than 100 percent of total volume for
table.AddlLmt quota
remove PCC rule types all for all
install 16Mbps_DL_5.76Mbps_UL PCC rules for flow
grant total volume to 100 percent used for table.AddlQuota
Advanced: set values for QoS and Charging parameters to
Diameter Enforcement Session Event Triggers  REVALIDATION_TIMEOUT,
USAGE_THRESHOLD_REACHED
Diameter IP-CAN Session Usage Monitoring  USAGE_MONITORING_ENABLED

accept message
```

Creating a Policy Table

When you define a policy table, it must contain at least one key column and one row, and you must populate every cell in the table.
To create a policy table:

1. From the **Policy Management** section of the navigation pane, select **Policy Table Library**.

The content tree displays the **All Tables** group.

2. Select the **Policy Tables** sub-group.

The Policy Table Administration page opens in the work area.

3. Click **Create Policy Table**.

The Policy Table Administration page opens.

4. Enter information as appropriate:

- a. **Name** (required) — The name you assign to the policy table.

The name can only contain the characters A–Z, a–z, 0–9, period (.), hyphen (-), and underline (_). The maximum length is 255 characters.

- b. **Description/Location** (required) — Free-form text that identifies the policy table.

5. To add a column, click **Add Column** (required) — You must define at least one key column.

Enter the following information:

- **Column Name** (required) — The name you assign to the column. Policies use this name as part of the address of cells in this column. The name can only contain the characters A–Z, a–z, 0–9, space (), and underline (_).
 - **Column Type** (required) — The data type of cells in the column. Click the folder icon; a selection window opens, displaying the Policy Wizard actions and conditions. Locate the condition or action you want to abstract and select the variable to use (displayed in red text); the data type is taken from the variable.
 - **Key** — The policy variable used as a key. If this is a key column, select the check box and either select a policy variable from the list or type the name of the variable you want to use. The policy variable is used to obtain the value from the policy context when using the table to look up a row.
 - **Delimiter** — The character that separates values within a cell. For fields that accept multiple values, specify the delimiter between values. Enter any single ASCII character. The default is a comma (,). If you enter no value, the field is evaluated as a single value.
 - **Matching Operation** — If this is a key column and no delimiter is defined, the default matching operation is **Equivalence**. If the column type is **Token List Name**, the matching operation is **Matchlist**. If a delimiter is defined, select the matching operation:
 - **Wildcard**
 - **Policy Context Set Contains All Multiple Valued Key Column**
 - **Multiple Key Column Set Contains Single Value Context** (default)
 - **Multiple Policy Context Set Contains Single Value Key Column**
 - **Key Column Value Set Contains Any Multiple Valued Context**
 - **Equivalence**
 - **Key Column Set Contains All Multiple Valued Policy Context**
 - **Matchlist** (available when column type is Token List Name)
- For information on matching operations see [About Data Matching](#).
- Click **Save**.

The column is created. If no rows exist, a row is created.

6. (Optional) You can add additional rows by doing the following:
 - a. Click **Add Row**. A row is added below the current row in the table.
 - b. Select a cell in the row. A window opens so you can enter the value for that cell. The data in the cell must match the data type of the column.
 - c. Enter the value and click **OK**. You can also enter a comma-separated list of values.

The row is created and appears below the previous row.

7. (Optional) You can manage columns and rows by selecting a column or row and clicking **Operations**, then selecting an operation from the list:
 - **Delete Row** — Deletes the table row.
 - **Move Row Up** — Moves the table row up.
 - **Move Row Down** — Moves the table row down.
 - **Delete Column** — Deletes the column in the table.
 - **Move Column Left** — Moves the column left in the table.
 - **Move Column Right** — Moves the column right in the table.
 - **Sort Column** — Sorts the column in the table.
 - **UnSort Column** — Reverts the column to its original order.

8. Click **Validate**.

Validation ensures that tables contain a key column, at least one row, and no empty cells. If the table is valid, a confirmation message appears. Click **OK** to close the window.

If the table is invalid, a diagnostic message appears. Correct the table, and click **Validate** again.

The table definition is validated.

9. Click **Save**.

The policy table is validated and is displayed on the Policy Table Administration page.

You have created a policy table. You can now use the table in a policy. [Policy Table](#) shows the sample policy table discussed in [Policy Table](#).

Figure 9-2 Sample Policy Table

Policy Table Administration

Policy Table: Quota_table

Modify Delete

Name: Quota_table
Description: Table for data plan quotas

scenario	BaseQuota	AddlQuota	PctLimit	AddlLimit	GrantQuota
100MB	DP_QUOTA.100MB	DP_QUOTA_ADDL.3GB	70	3GB	DP_QUOTA_ADDL.3GB
2GB	DP_QUOTA.2GB	DP_QUOTA_ADDL.4GB	90	4GB	DP_QUOTA_ADDL.4GB
100GB	DP_QUOTA.100GB	DP_QUOTA_ADDL.5GB	90	5GB	DP_QUOTA_ADDL.5GB

Viewing Policy Tables

To view a policy table:

1. From the **Policy Management** section of the navigation pane, select **Policy Table Library**.

The content tree displays the **All Tables** group.

2. Select the **Policy Tables** sub-group.

The Policy Table Administration page opens in the work area.

3. Click the policy table name in the content tree.

The policy table details are displayed in the work area.

Associating a Policy Table with a Policy Rule

To associate a policy table with a new or existing policy rule, the policy table must already be created. See [About Policy Tables](#) for more information on what a policy table is. See [Creating a Policy Table](#) for more information on how to create a policy table. See [Creating a Policy Rule](#) for more information on creating and modifying a policy definition.

To associate a policy table with a policy rule:

1. From the **Policy Management** section of the navigation pane, select **Policy Library**.

The content tree displays the **All Tables** group.

2. Select the **Policy Tables** sub-group.

The Policy Table Administration page opens in the work area.

3. Select the policy you want to associate to a policy table.
The Policy Administration page displays information about the policy.
4. Click **Modify**.
The policy wizard opens in a Modify Policy tab.
5. At the bottom of the page, click **Tables**.
The Table Associations page opens in the Modify Policy tab.
6. On the Table Associations page, select the association type.
 - **use table *policy table* called *specified alias name***
 - **use table *policy table* called *specified alias name* returns *unique row***

 Note:

If unique row is selected, this option acts as same as the "use table *policy table* called *specified alias name*

- The policy table option is added to the Description section of the page, where you select an existing policy table to use and define an alias name for this policy table, if needed.
7. In the Description section of the page, click ***policy table***.
The Policy Table Data window appears.
 8. Select a table, and click **OK**.
 9. Click ***specified alias name***.
The Input a Value window opens.
 10. Enter an alias name in the format specified in the window, and click **OK**.
The name describes the purpose of this table in this policy. You can then use the same policy table in multiple policies but define a different purpose each time with the alias name field.
 11. If you selected the table association that specifies unique row option, click **unique row** and select an option.
 - **unique row** (default) — First matched row is selected.
 - **multiple rows** — All matches are selected.
 12. Repeat these steps to associate another policy table with this policy rule, if needed.
 13. If multiple policy tables are associated with this policy rule, use the ▲ (up) icon or ▼ (down) icon to move the table and change the order in which it is evaluated in the rule.
 14. At the bottom of the page, click **Name**.
The Name page opens on the Modify Policy tab.
 15. Click **Finish**.
The selected policy tables are associated with this policy definition.

Associating a Parameter with a Policy Table Column

After you have defined a policy table and associated it with a policy rule, you can associate individual rule parameters with columns (fields) defined in the table.

To associate a parameter with a policy table column:

1. In the condition or action, click on the parameter for which you want to use the policy table.

A selection window opens.

2. Click **Use Policy Table**.

A list of policy table fields (columns) opens.



Tip:

If no choices are available, no appropriate column is defined.

3. Select the policy table field (column) and click **OK** to use that field, or **Use Input Value** to enter an input value (not use the policy table) instead.

The selection window closes.

When the rule is evaluated, the value of the parameter is replaced by the value in the policy table.

Modifying a Policy Table

To modify a policy table:

1. From the **Policy Management** section of the navigation pane, select **Policy Table Library**.

The content tree displays the **All Tables** group.

2. Select the **Policy Tables** sub-group.

The Policy Table Administration page opens in the work area.

3. Select the policy table you want to modify.

The Policy Table Administration page opens, displaying information about the policy table.

4. Click **Modify**.

The table fields become editable. See [Creating a Policy Table](#) for information about the table fields.

5. Click **Validate**.

The data modified is validated. If the table is valid, a confirmation message displays. Click **OK** to close the window. If invalid, a diagnostic message appears.

6. Click **Save**.

The policy table content is modified. A notification message listing the differences is displayed if the policy table is the default or associated policy table for a virtual policy table, if the policy

table structure has been modified, or if the policy table columns contain differences between delimiters, matching operations, or keys.

Deleting a Policy Table

To delete a policy table:

1. From the **Policy Management** section of the navigation pane, select **Policy Table Library**.

The content tree displays the **All Tables** group.

2. Select the **Policy Tables** sub-group.

The Policy Table Administration page opens in the work area.

3. Delete the policy table using one of the following methods:

- From the work area, click  (trash can icon) located to the right of the policy table.
- Open the policy and click **Delete**.

A confirmation message appears.

4. Click **OK**.

The policy table is deleted.

Managing Policy Groups

Policy groups are an organizational aid that provide for flexible policy management, deployment, and execution. You save policies to a group in the order in which you want an MPE device to apply them to a policy request. If needed, you can change that order. You can save a policy to multiple policy groups and add a policy to, or remove it from, a policy group at any time. You can also nest policy groups.

This chapter describes how to create, modify, and delete policy groups.

Creating a Policy Group

To create a policy group:

1. From the **Policy Management** section of the navigation pane, select **Policy Library**.
The content tree displays a list of policy library groups; the initial group is **ALL**.
2. From the content tree, select the **ALL** group.
The Policy Administration page opens in the work area.
3. Click **Create Group**.
The **Name** field opens in the work area.
4. Enter the name to assign to the new group.
The name can only contain the characters A–Z, a–z, 0–9, period (.), hyphen (-), and underline (_). The maximum length is 64 characters.
5. Click **Save**.

The new group information is saved to the CMP database and displayed in the content tree.

Adding a Policy or a Policy Group to a Policy Group

After you create a policy group, you can add policies to the group. You can also add policy groups to a policy group.



Note:

Oracle recommends that you nest policy groups only two levels deep.

To add policies or policy groups to a policy group:

1. From the **Policy Management** section of the navigation pane, select **Policy Library**.
The content tree displays a list of policy library groups; the initial group is **ALL**.
2. From the content tree, select the **ALL** group.

The Policy Administration page opens in the work area, listing the defined policies and policy groups.

3. Select the policy group to which you want to add the policy or policy group.

The Policy Administration page opens in the work area, listing the policies and policy groups currently in the selected group.

4. Click **Modify**.

The Policy Administration page opens in the work area.

5. Click **Add**.

A window opens, displaying the policies and policy groups available.

6. (Optional) You can filter the list by selecting one of the following:

- **Policy** — Displays the policies in the group.
- **Group** — Displays the policy groups in the group.
- **All** (default) — Displays both the policies and the policy groups in the group.

7. Select the policy or group to add to this group and click **Add**. Use Shift/click to select multiple policies or policy groups. By default, policies and policy groups are added after the first item in the group; to change the insert position, change the value in the **Location** field.

The policies or policy groups are added to the policy group in the specified location and the window closes.

 Note:

Policies or policy groups are applied to messages in the order in which they appear in the policy group. You can change the sequential order (see [Changing the Sequence of Deployed Policies on an MPE Device](#)).

8. Click **Save**.

The added policies and policy groups are displayed in the policy group tree. You can deploy the policy group. For more information about deploying policies and policy groups, see [Deploying a Policy](#).

 Note:

If this group had been deployed previously, it is automatically redeployed at this time, ensuring the MPE devices are synchronized with the CMP database.

Displaying Details of All Policies in a Policy Group

To display the details of all policies in a policy group:

1. From the **Policy Management** section of the navigation pane, select **Policy Library**.

The content tree displays a list of policy library groups; the initial group is **ALL**.

2. From the content tree, select the policy group that you want to display.

The Policy Administration page opens in the work area, displaying the list of policies and policy groups in the selected group.

3. Click **Show Details**.

The configured policies, including the configured parameters for the policies, are displayed. To switch between views, click **Toggle View**.

4. Click **Cancel**.

The details of all policies in the group appears.

Changing the Sequence of Policies or Policy Groups Within a Policy Group

The sequence in which policies or policy groups appear in a policy group is the order in which they are deployed and applied to policy requests. You can modify the sequence of policies or policy groups, both inside and outside of a policy group.

To change the sequence of the policies or policy groups within a policy group:

1. From the **Policy Management** section of the navigation pane, select **Policy Library**.

The content tree displays a list of policy library groups; the initial group is **ALL**.

2. From the content tree, select the policy group that contains the policies or policy groups that you want to reorder.

The Policy Administration page opens in the work area, displaying the list of policies and policy groups in the selected group. They are displayed in sequential order.

3. Click **Modify**.

The Manage Policies page opens.

4. Change the sequence of policies or policy groups within the group by doing one of the following:

- Use the  (top) and  (bottom) icons, located to the left of policies or policy groups. The  (top) icon moves the item it to the top of the list. The  (bottom) icon moves the item it to the bottom of the list.
- Drag and drop policies or policy groups to a different position in the sequence.
- Change the sequence numbers, located to the left of policies or policy groups. Click **Update Order** to refresh the display.
- Optionally, you can click **Undo** or **Redo** to step back and forth through your changes.

5. Click **Save**.

The modified policy group is automatically redeployed, ensuring that the MPE devices are resynchronized with the CMP database.



Note:

If the policy group has never been deployed, you can now deploy it. For more information about deploying policies and policy groups, see [Deploying a Policy](#).

Removing a Policy from a Policy Group

Removing a policy from a policy group that has been saved to the CMP database removes the policy from only the selected policy group. The policy remains in the **ALL** group, as well as any other group to which it had been added. (To remove a policy from all groups in the Policy Library, see [Removing a Policy from an MPE Device](#).) To remove a policy from a policy group:

1. From the **Policy Management** section of the navigation pane, select **Policy Library**.

The content tree displays a list of policy library groups; the initial group is **ALL**.


2. From the content tree, select the policy group from which you want to delete a policy.

The Policy Administration page opens in the work area, displaying the list of policies and policy groups in the selected group.

3. To remove the policy, from the content tree, select the policy within the policy group.

The profile information for the policy is displayed.

Figure 10-1 Policy within a Policy Group




4. Click **Remove**.

The selected policy is removed from the policy group.

5. Alternatively, from the content tree, select the policy group and click **Modify**.

Figure 10-2 Removing a Policy from a Policy Group



- Click the remove icon, located to the right of the policy you want to remove.

The selected policy is removed from the policy group.

The modified policy group is automatically redeployed, ensuring that the MPE devices are resynchronized with the CMP database.



Note:

If the policy group has never been deployed, you can now deploy it. For more information about deploying policies and policy groups, see [Deploying a Policy](#).

Managing Analytics Data Stream Generation for a Policy Group

You can enable or disable generation of an analytics data stream (ADS) for all policies in a group. See *Analytics Data Stream Reference* for more information on the Oracle Communications Policy Management Analytics product.



Note:

To enable or disable ADS generation at a policy group level, you must configure the **Manage Analytic Data** management option to enable the ADS feature. See the appropriate *CMP User's Guide* for more information.

Deleting a Policy Group

Deleting a policy group removes the policy group from all policy groups to which it has been added.

To delete a policy group:

- From the **Policy Management** section of the navigation pane, select **Policy Library**.

The content tree displays a list of policy library groups; the initial group is **ALL**.

2. From the content tree, select the policy group that you want to delete.

The Policy Administration page opens in the work area, displaying the list of policies and policy groups in the selected group.

3. Click **Delete**.

A confirmation message appears.

4. Click **OK**.

The policy group is deleted from the CMP database. Any policy groups that contained the deleted policy group are automatically redeployed, ensuring that the MPE devices are synchronized with the CMP database.

Managing Policy Templates

The CMP system lets you create policy templates to simplify the creation of multiple policies with similar conditions and actions. A policy template is similar to a policy, except that some (or all) of the parameters in the conditions and actions are not completely defined. Those parameters are defined later, when you use the policy template to create policy rules.

The policy template wizard is used to create or modify a policy template. This wizard is similar to the policy wizard; however, the policy template wizard allows parameters to be only partially defined. For example, a template may be configured for only policy requests requiring bandwidth above a certain value, but not define the exact bandwidth value. You can then specify a specific bandwidth value when you use the template to create the new policy rule.

This chapter describes how to create, modify, and delete policy templates.

Creating a Policy Template

To create a policy template:

1. From the **Policy Management** section of the navigation pane, select **Template Library**.
The content tree displays the **Template Library** group.
2. From the content tree, select the **Template Library** group.
The Template Administration page opens in the work area.
3. Click **Create Template**.
The Create New Policy Template window opens.
4. Select the base policy or policy template with which to begin:
 - **Blank** — No policy template attributes are predefined.
 - **Use Template** — Select an existing template with predefined attributes. Modify the template as needed, then save the template with a new template name.
 - **Copy Existing Policy** — Select an existing policy. Modify the policy, then save the policy as a policy template.
5. Edit the policy information from one or more of the policy wizard pages.
See [Creating a Policy Rule](#) for details on the fields within the policy wizard.
6. Click **Finish**.

The policy template is created.

Modifying a Policy Template

Modifying a policy template does not modify previously configured policies.

To modify a policy template:

1. From the **Policy Management** section of the navigation pane, select **Template Library**.

The content tree displays the **Template Library** group.

2. From the content tree, select the **Template Library** group.

The Template Administration page opens in the work area, displaying a list of all defined policy templates.

3. Select the template you want to modify.

The Template Administration page displays a description of the template.

4. Click **Modify**.

The **Modify Policy** tab opens, showing the last step of the template creation process.

5. Click **Back** to return to the page you want to edit and modify the information.

6. Click **Finish**.

The template is modified.

Deleting a Policy Template

To delete a policy template:

1. From the **Policy Management** section of the navigation pane, select **Template Library**.

The content tree displays the **Template Library** group.

2. From the content tree, select the **Template Library** group.

The Template Administration page opens in the work area, displaying a list of all defined policy templates.

3. Delete the policy template using one of the following methods:

- From the work area, click  (trash can icon), located to the right of the policy template.
- From the content tree, select the template and click **Delete**.

A confirmation message appears.

4. Click **OK**.

The policy template is deleted.

Managing Virtual Policy Tables

This chapter describes how to create, modify, and delete virtual policy tables, which are manageable objects that you can use to deploy policy table data to individual MPE devices. You can test policy table changes on a subset of your network by using configuration templates to associate multiple policy tables to a single virtual policy table.

About Virtual Policy Tables

Virtual policy tables allow you to deploy policy table data to specific MPE devices without affecting the entire network. You can use virtual policy tables to test configurations and changes before you deploy them to the entire network. Unlike policy tables, virtual policy tables do not contain any data except for pointers to policy tables and configuration templates. Virtual policy tables are available in the policy wizard.

A virtual policy table points to one default policy table and may point to one or more associated policy tables that are specified by a configuration template. The default policy table specifies the policy table data that is pushed to MPE devices on the network by default. In the absence of any associated policy tables, a virtual policy table behaves like its' default policy table. You can use a configuration template to associate additional policy tables to the virtual policy table and to specify which MPE devices should use the associated policy table data instead of the default policy table data. For information about using configuration templates, see the appropriate *CMP User's Guide*.

The following validations exist for virtual policy tables:

- A virtual policy table must not share a name with any other policy tables or virtual policy tables.
- A virtual policy table must be deleted before its' default policy table or associated policy tables can be deleted.
- A virtual policy table can only be assigned a new default policy table if the virtual policy table is not used in any policies and if all of the associated policy tables contain at least the columns contained in the new default policy table.
- A virtual policy table can be assigned associated policy tables as long as the associated policy tables contain at least the same column names and types as the default policy table.

The following validations exist for policy table columns when the policy table is either a default or an associated policy table for a virtual policy table:

- A policy table column can be modified in a default policy table if the column is not used in any policies and if the newly modified column is contained in all associated policy tables.
- A policy table column can be removed from a default policy table if the column is not used in any policies.
- A policy table column can be removed from or modified in an associated policy table if the column is not contained in the default policy table for any virtual policy tables to which the policy table is associated.

Virtual Policy Table Case Study

Virtual policy tables allow you to test policy table deployments before you deploy them to the entire network.

A wireless carrier named Example Inc. offers three monthly data usage plans for its subscribers. The monthly quota levels are 100 MB, 2 GB, and 100 GB, and each level corresponds to one row in the policy table. The business logic for each usage plan is captured using one policy table, Monthly Data Plans, with six columns and three rows, as shown in the table below. For a detailed explanation of this policy table, see [Policy Table Case Study](#).

Table 12-1 Monthly Data Plans Policy Table

Policy Variable scenario	Base Quota	Additional Quota	Percent Limit	Additional Limit	Grant Quota
100 MB	DP_QUOTA.100 MB	DP_QUOTA_ADDL. 3GB	70	3 GB	DP_QUOTA_ADDL.3GB
2 GB	DP_QUOTA.2GB	DP_QUOTA_ADDL. 4GB	90	4 GB	DP_QUOTA_ADDL.4GB
100 GB	DP_QUOTA.100 GB	DP_QUOTA_ADDL. 5GB	90	5 GB	DP_QUOTA_ADDL.5GB

Any changes to the Monthly Data Plans policy table will be deployed to the entire network. To test changes without deploying them to the entire network, Example Inc. creates a virtual policy table, Test Plans, and sets the default policy table for Test Plans to Monthly Data Plans. Without further configuration, changes made to the Monthly Data Plans policy table will be deployed to the entire network as before.

Example Inc. requires an additional monthly data usage plan for its subscribers with a monthly quota level of 150 GB. To test the policies associated with the 150 GB monthly data usage plan, Example Inc. creates a second policy table, Four-tier Data Plans, with the same rows and columns as Monthly Data Plans and an additional row to represent the 150 GB usage plan. The Four-tier Data Plans policy table is associated to the Test Plans virtual policy table using a configuration template.

Table 12-2 Four-tier Data Plans Policy Table

Policy Variable scenario	Base Quota	Additional Quota	Percent Limit	Additional Limit	Grant Quota
100 MB	DP_QUOTA.100 MB	DP_QUOTA_ADDL. 3GB	70	3 GB	DP_QUOTA_ADDL.3GB
2 GB	DP_QUOTA.2GB	DP_QUOTA_ADDL. 4GB	90	4 GB	DP_QUOTA_ADDL.4GB
100 GB	DP_QUOTA.100 GB	DP_QUOTA_ADDL. 5GB	90	5 GB	DP_QUOTA_ADDL.5GB

Table 12-2 (Cont.) Four-tier Data Plans Policy Table

Policy Variable Scenario	Base Quota	Additional Quota	Percent Limit	Additional Limit	Grant Quota
150 GB	DP_QUOTA.150 GB	DP_QUOTA_ADDL.6GB	90	6 GB	DP_QUOTA_ADDL.6GB

The Test Plans virtual policy table now has one default policy table, Monthly Data Plans, and one associated policy table, Four-tier Data Plans. The data in the Monthly Data Plans policy table is pushed to all of the MPE devices on the network except when the configuration template specifies that the data in the Four-tier Data Plans policy table should be pushed instead. Example Inc. can now test the new 150 GB monthly data usage plan on a specific MPE devices without affecting the rest of the network.

If the testing is successful, the added row from the Four-tier Data Plans policy table can be added to the Monthly Data Plans policy table and deployed to the entire network. The Four-tier Data Plans policy table can safely be deleted or removed from the Test Plans virtual policy table configuration.

Creating a Virtual Policy Table

To create a virtual policy table:

1. From the **Policy Management** section of the navigation pane, select **Policy Table Library**.

The content tree displays the **All Tables** group.

2. Select the **Virtual Policy Tables** sub-group.

The Virtual Policy Table Administration page opens in the work area.

3. Click **Create Virtual Policy Table**.

The Virtual Policy Table Administration page opens.

4. Enter information as appropriate:

- a. **Name** (required) — The name you assign to the virtual policy table.

The name can only contain the characters A–Z, a–z, 0–9, period (.), hyphen (-), and underline (_). The maximum length is 255 characters. The name must not match any existing policy table or virtual policy table names.

- b. **Default Policy Table** (required) — The policy table to which the virtual policy table points by default.

- c. **Description/Location** — Free-form text that identifies the virtual policy table.

5. (Optional) To associate the virtual policy table with a configuration template, click **Add**.

The **Add Virtual Policy Table Association** dialog box appears.

6. Select a configuration template and a policy table from the list.

Associated policy table columns must have the same name and type as those in the default policy table.

7. Click **Save**.

The configuration template is associated with the virtual policy table.

8. Click **Save**.

The virtual policy table is created. You can now use the virtual policy table to deploy policy tables to specific MPE devices. If the default and associated policy tables contain different keys, delimiters, or matching operations, a notification message listing the differences is displayed.

When the virtual policy table is created, it is added to the CMP database and pushed to all MPE devices. If the virtual policy table does not have an associated configuration template or if the associated configuration template is not associated with an MPE, the default policy table data for the virtual policy table is pushed to all MPE devices. If there is an associated configuration template and the template is associated with MPE devices, policy table data is pushed to MPE devices as specified in the configuration template.

Modifying Virtual Policy Tables

To modify a virtual policy table:

1. From the **Policy Management** section of the navigation pane, select **Policy Table Library**.

The content tree displays the **All Tables** group.

2. Expand the **Virtual Policy Tables** sub-group.

The Virtual Policy Table Administration page opens in the work area.

3. Select a virtual policy table.

The Virtual Policy Table Administration page displays information about the virtual policy table.

4. Click **Modify**.

The Virtual Policy Table Administration becomes editable. See [Creating a Virtual Policy Table](#) for information about configuring a virtual policy table.

5. Click **Save**.

The virtual policy table is modified. If the default and associated policy tables contain different keys, delimiters, or matching operations, a notification message listing the differences is displayed.

Deleting Virtual Policy Tables

To delete a virtual policy table:

1. From the **Policy Management** section of the navigation pane, select **Policy Table Library**.

The content tree displays the **All Tables** group.

2. Select the **Virtual Policy Tables** sub-group.

The Virtual Policy Table Administration page opens in the work area.

3. Delete the virtual policy table using one of the following methods:

- From the work area, click  (trash can icon) located to the right of the virtual policy table.
- Open the virtual policy table and click **Delete**.

A confirmation message displays.

4. Click **OK**.

The virtual policy table is deleted.

Managing Policy Checkpoints

This chapter describes the method of saving CMP objects and their configuration and their association to the CMP database at a specific point in time.

About Policy Checkpoints

A policy checkpoint is a method of saving the records in the CMP database at a specific point in time. The table below details which configurable objects are and are not saved as part of the checkpoint.

Table 13-1 Record Keeping and Policy Checkpoints

Records saved	Records not saved
• policies • policy groups • policy templates • policy tables • policy counter IDs • traffic profiles • traffic profile groups • MPE configuration templates • match lists • retry profiles • applications	• quota profiles • quota conventions • serving gateways/MCC-MNC mappings • charging servers • time periods • customer AVPs • services • rating groups • LI mediation functions



Note:

The checkpoint function also saves associations between:

- Virtual MPE templates and real MPE templates
- MPE devices and virtual MPE templates
- Virtual MPE templates and other configuration objects

You can save up to 10 checkpoints.

After a checkpoint is created, you can return to this set of records at any time by restoring the checkpoint.



Caution:

When you restore a checkpoint, all existing data is permanently removed.

The checkpoint function is different from the import/export function in the following ways:

- Checkpoints are saved to the CMP database rather than to a file.
- A checkpoint saves all the records mentioned in the preceding table. The import/export feature allows you to select which records to import or export.
- A checkpoint can only be used on a specific CMP system and cannot be migrated to another CMP system.

Creating a Policy Checkpoint

To access this feature, specify a value greater than 0 for the **Allow policy backup and rollback** field on the System Settings page. To refresh the menu, log out and log back in. This field also controls the maximum number of checkpoints that can be saved. For information on system settings, see the appropriate *CMP User's Guide*.

Use this procedure to create a new checkpoint. A checkpoint saves policies, policy groups, policy templates, policy tables, traffic profiles, and traffic profile groups; other records are not saved.

Note that the maximum number of checkpoints that can be created is defined on the System Settings page. If you create more than the number defined, the oldest checkpoint is deleted.

To create a new policy checkpoint:

1. From the **Policy Management** section of the navigation pane, select **Policy Checkpoint/Restore**.
The Checkpoint/Restore page opens.
2. Click **Create a new checkpoint**.
If the maximum number of checkpoints already exists, you are prompted, *n checkpoints already exist, by creating this checkpoint the oldest one will be deleted. Continue? where n indicates the maximum number of checkpoints*).
3. Click **OK**.
The checkpoint is created.

Viewing and Comparing Policy Checkpoints

To view/compare policy checkpoints in the CMP database:

1. From the **Policy Management** section of the navigation pane, select **Policy Checkpoint/Restore**.
The Checkpoint/Restore page opens.
2. Click **Diff** to view a report that compares the selected checkpoint's records to the current CMP records.
3. Click **More Info** to view a list of all required profile names for this checkpoint. These profiles must exist in the system before a checkpoint is restored, otherwise the restore will fail.

Restoring a Policy Checkpoint

Caution:

All current records are lost when a restore is performed. Oracle recommends that you save a checkpoint before restoring a previous checkpoint.

Note:

Charging servers, customer AVPs, services, LI mediation functions, rating groups, serving gateways/MCC-MNC mappings, and time periods are not saved in checkpoints, so be sure all related profile information exists in the CMP system before restoring. If related profile information is not available before you do a restore, the restore process will fail. Use the **More Info** link to view all required profile information for a checkpoint.

To restore to a checkpoint in the CMP database without autodeployment to the MPE devices:

1. From the **Policy Management** section of the navigation pane, select **Policy Checkpoint/Restore**.

The Checkpoint/Restore page opens.

2. Click **Restore**.
3. Select the checkpoint you are restoring.
4. Click **Restore**.

You are prompted, **Caution: All current records are lost when a restoration is performed. It is recommended that you save a checkpoint before restoring a previous checkpoint. Are you sure that you want to restore to this Checkpoint?**

5. Click **OK**.

A confirmation message appears.

6. Click **OK**.
7. Click **Save**.

A checkpoint report appears, listing which policies and policy groups were restored and which were removed.

Restoring a Policy Checkpoint to MPE Devices

Caution:

All current records are lost when a restore is performed. Oracle recommends that you save a checkpoint before restoring a previous checkpoint.



Note:

Charging servers, customer AVPs, services, LI mediation functions, rating groups, serving gateways/MCC-MNC mappings, and time periods are not saved in checkpoints, so be sure all related profile information exists in the CMP system before restoring. If related profile information is not available before you do a restore, the restore process will fail. Use the **More Info** link to view all required profile information for a checkpoint.

To restore to a checkpoint in the CMP database and autodeploy to all MPE devices in the system:

1. From the **Policy Management** section of the navigation pane, select **Policy Checkpoint/Restore**.

The Checkpoint/Restore page opens.

2. Click **Restore**.
3. Select the checkpoint you are restoring.
4. Click **Restore and Deploy**.

You are prompted, Caution: All current records are lost when a restoration is performed. It is recommended that you save a checkpoint before restoring a previous checkpoint. Are you sure that you want to restore to this Checkpoint and deploy it to MPEs?

5. Click **OK**.

A confirmation message displays.

6. Click **OK**.

7. Click **Save**.

A checkpoint report appears, listing which policies and policy groups were restored, which were removed, and to which MPE devices the deployment succeeded.

Deleting a Policy Checkpoint

To delete a saved checkpoint from the CMP system:

1. From the **Policy Management** section of the navigation pane, select **Policy Checkpoint/Restore**.

The Checkpoint/Restore page opens.

2. Select the checkpoint you are deleting.
3. Click **Delete the selected checkpoint**.
4. Click **OK**.

A confirmation message appears.

The selected checkpoint is deleted from the CMP database.

Part II

Configuring Manageable Objects for Use In Policies

Part II describes how to create and manage the manageable objects that are available to be used in policies.

About Creating Manageable Objects

The manageable object creation tasks you need to perform depend on whether you are operating a cable, wireless, or wireline network and what services and servers exist in your network. You must create an object before you can use it in a policy. You can create the objects in any order, at any time.

The following sections list the manageable objects by operating mode:

- [Wireline Mode Object](#)
- [Wireless Mode Objects](#)
- [Cable Mode Objects](#)



Note:

You can also use the administrative **Import / Export** function to quickly and easily import multiple manageable objects. See the appropriate *CMP User's Guide* for detailed information.

After you have created your manageable objects, you are ready to create and manage policy rules. See [Managing Policy Rules](#) for descriptions of tasks and references to these tasks.

Wireless Mode Objects

The manageable objects for Wireless mode of the CMP system are:

- Create application profiles, which specify protocol information to associate each request with an application. This task is described in [Managing Application Profiles](#).
- Create custom attribute-value pairs (AVPs), which are used to encapsulate protocol-specific information with usage monitoring supported by MPE devices in a wireless network. This task is described in [Managing Custom AVPs](#).
- Create match lists, which create whitelists and blacklists in a wireless network. This task is described in [Managing Match Lists](#).
- Create monitoring keys, which associate quota profiles with policy and charging control (PCC) and application detection control (ADC) rules for usage tracking in a wireless network. This task is described in [Managing Monitoring Keys](#).
- Create policy counter identifiers, which define the name, optional description, and default online charging server (OCS) value for which status can be received from the OCS server in a wireless network. This task is described in [Managing Policy Counter Identifiers](#).
- Create policy time periods, which are used in policy time-of-day conditions in a wireless network. This task is described in [Managing Policy Time Periods](#).

- Create Presence Reporting Area (PRA) lists, which specify areas that can be used in location-specific policies in a wireless network. This task is described in [Managing Presence Reporting Area Lists](#).
- Create quotas, which set a limit on a subscriber's usage in a wireless network. This task is described in [Managing Quotas](#).
- Create quota passes, which comprise rollovers and top-ups, in a wireless network. This task is described in [Managing Quota Conventions](#).
- Create retry profiles, which specify the circumstances under which installation of a PCC rule is retried if the rule is reported to have failed in a wireless network. This task is described in [Managing Retry Profiles](#).
- Create Gy services, which identify a class of traffic, and rating groups, which are collections of services, in a wireless network. This task is described in [Managing Services and Rating Groups](#).
- Create custom vendors, which are used to support new vendors in a RADIUS Change of Authorization (CoA) message. This task is described in [Managing Custom Vendors](#).
- Create custom vendor-specific attributes (VSAs), which are used to encapsulate data specific to a non-standard vendor device. This task is described in [Managing Custom VSAs](#).
- Create RADIUS Change of Authorization (CoA) templates, which are used by MPE devices to respond to RADIUS CoA messages. This task is described in [Managing RADIUS CoA Templates](#).
- Create subscriber keys, which are used to identify subscribers based on information received in RADIUS messages. This task is described in [Managing Subscriber Keys](#).
- Create traffic profiles, which define default settings for protocol messages. This task is described in [Managing Traffic Profiles](#).

Cable Mode Objects

The manageable objects for Cable mode of the CMP system are:

- Create application profiles, which specify protocol information to associate each request with an application. This task is described in [Managing Application Profiles](#).
- Create media profiles, which describe audio and video CODECs supported for Rx-to-PCMM translation in a cable network. This task is described in [Managing Media Profiles](#).
- Create service classes, which correspond to Data-Over-Cable Service Interface Specification (DOCSIS) traffic descriptions defined in cable modem termination systems (CMTSS) in a cable network. This task is described in [Managing Service Classes](#).
- Create custom vendors, which are used to support new vendors in a RADIUS Change of Authorization (CoA) message. This task is described in [Managing Custom Vendors](#).
- Create custom vendor-specific attributes (VSAs), which are used to encapsulate data specific to a non-standard vendor device. This task is described in [Managing Custom VSAs](#).

- Create subscriber keys, which are used to identify subscribers based on information received in RADIUS messages. This task is described in [Managing Subscriber Keys](#).
- Create traffic profiles, which define default settings for protocol messages. This task is described in [Managing Traffic Profiles](#).

Wireline Mode Object

The manageable object for Wireline mode of the CMP system is:

- Create application profiles, which specify protocol information to associate each request with an application. This task is described in [Managing Application Profiles](#).

Managing Application Profiles

This chapter describes how to create and manage application profiles within the CMP system.

An application is a service provided to network subscribers for which you want to manage Quality of Service (QoS).

About Application Profiles

An **application** is a service provided to users of your network for which you want to manage quality of service (**QoS**). Examples include voice over IP (**VoIP**) telephony, video on demand (VoD), and gaming. After you have defined an application profile in the CMP database, you can associate it with the MPE devices that will manage that application.

When you offer application services in your network, there are typically many servers in your network that provide that service. These servers are referred to as Application Managers or Application Servers. When these servers are establishing a session that requires quality of service they issue a request to a policy charging and rules function (PCRF). The MPE device provides PCRF for the CMP server.

When defining an application profile in the CMP database, you specify protocol information that is used by MPE devices to identify Application Managers and thus associate each request with its associated application. This lets the MPE device apply policy rules to the request that you have defined for the associated application.

Creating an Application Profile

To create an application profile:

1. From the **Policy Server** section of the navigation pane, select **Applications**.
The content tree displays the **Applications** group.
2. Select the **Applications** group.
The Application Administration page opens in the work area.
3. Click **Create Application**.
The New Application page opens.
4. Enter the following application profile information:
 - a. **General Configuration:**
 - **Name** — Name assigned to the application. The name can only contain the characters A–Z, a–z, 0–9, period (.), hyphen (-), and underline (_). The maximum length is 250 characters.
 - **Description/Location** (optional) — Free-form text.
 - **Connection IP Addresss** — Enter the IP addresses, in IPv4 or IPv6 format, that are used by Application Managers for this application. To include an address in

the connection list, type it and click **Add**; to remove an address from the list, select it and click **Delete**.

- **Latency Sensitive** — Select this option if the application is latency sensitive.

b. **Policy Servers associated with this Application:** select a policy server (MPE device) to associate with this network element.

c. **License Tracking:**

- **Tracked** — Select **Yes** (default) if the sessions for the application are associated with a license. Otherwise, select **No**.
- **Flows per Session** — Specifies the number of upstream and downstream sessions (1 to 4) that are allocated to this application.
- **License Timeout** — Specifies the duration of time for which this application requires a license. The default is 240 minutes (4 hours).

d. **PCMM:**

- **Application Manager IDs** — Enter the PCMM AMIDs that are used by Application Managers for this application. Click **Add** to define multiple values. To delete an existing value, select it from the list and click **Delete**.
- **Session Class IDs** — Enter the Session Class IDs that are used by each Application Manager for this application. Click **Add** to define multiple values. To delete an existing value, select it from the list and click **Delete**.

e. **Diameter:**

- **Diameter Identity** — Enter the Diameter identity (typically an FQDN) or identities used by application functions for this application. Click **Add** to define multiple values. To delete an existing value, select it from the list and click **Delete**.
- **AF Application ID** — Enter the ID for any application functions associated with the application, (for example, af-application-id1).
- **APN Match Lists** — Click **Manage...** to open the Select Match Lists for APNs. Select one or more APNs from the **Available** field and move them to the **Selected** field by clicking **-->** (right arrow). To move selected APNs to the available field, click **<--** (left arrow).

5. Click **Save**.

The application profile is created. The profile is stored in the **Applications** group and is available for use in a policy.

Modifying an Application Profile

To modify an application profile:

1. From the **Policy Server** section of the navigation pane, select **Applications**.

The content tree displays the **Applications** group.

2. Select the **Applications** group.

The Application Administration page opens in the work area, listing the application profiles.

3. Select the application profile.

The profile is displayed.

4. Click **Modify**.

The Modify Application page opens.

5. Modify the application profile information.

See [Creating an Application Profile](#) for a description of the fields on this page.

6. Click **Save**.

The application profile is modified.

Deleting an Application Profile

To delete an application profile:

1. From the **Policy Server** section of the navigation pane, select **Applications**.

The content tree displays the **Applications** group.

2. Select the **Applications** group.

The Application Administration page opens in the work area.

3. Delete the application profile using one of the following methods:

- From the work area, click the  (trash can icon), located to the right of the profile.
- From the content tree, select the application and click **Delete**. A confirmation message displays.

4. Click **OK**.

The application profile is deleted from the CMP database and all MPE devices.

16

Managing Custom AVPs

This chapter describes how to create, modify, and delete custom third-party attribute-value pairs (AVPs) in the CMP system.

In a wireless network, custom AVPs are used to encapsulate protocol-specific data for routing, authentication, authorization, and accounting information.

About Custom AVPs

An attribute-value pair (AVP) is used to encapsulate protocol-specific information with usage monitoring supported by the MPE device. Diameter messages such as RAA, CCA, CCR, and RAR are supported by third-party AVP policy conditions. The supported outgoing Diameter messages set or remove third-party AVPs.



Note:

The Diameter messages listed are examples only. There are many messages associated with Diameter.

You can create policy conditions to evaluate the presence of both standard (base) and third-party AVPs in Diameter messages or group AVPs during policy execution. A policy condition can check for the presence of both standard and third-party AVPs in incoming Diameter messages and evaluate their values. A policy action can use standard and third-party AVPs for routing, authentication, authorization, and accounting.

Standard AVPs can be included in third-party AVP conditions and actions. To include a standard (base) AVP in a nonstandard application message, or to use a pre-standard AVP as a standard AVP, define it as a custom AVP.

When defined, custom AVPs are located at the end of a parent Diameter message or group AVP. If the parent AVP is null, the custom AVP is inserted at the root level of the message. For example, a custom AVP definition appears at the end of this Charging-Rule-Install message:

```
Charging-Rule-Install ::= < AVP Header: 1001 >
*[ Charging-Rule-Definition ]
*[ Charging-Rule-Name ]
*[ Charging-Rule-Base-Name ]
[ Bearer-Identifier ]
[ Rule-Activation-Time ]
[ Rule-Deactivation-Time ]
[ Resource-Allocation-Notification ]
[ Charging-Correlation-Indicator ]
*[ customAVP ]
```

A Set or Get SPR user attribute value can be set to the defined third-party AVP in Diameter messages. You can also set or remove defined third-party AVPs during the execution point.

A third-party AVP is identified by a unique identifier in the following format:

name:vendorId

For example:

Condition

where the request AVP *NEW_AVP3:555* value is numerically equal to 2012

Parameters

The AVP name and vendor ID. In the example, the vendor ID is 555.

Description

A well-defined AVP custom name is referred to if the vendor ID is not specified.

When entering and sending a new third-party AVP definition to an MPE or MRA device, the definition must include the AVP name, code, vendor ID, data type, and an optional AVP flag.

Validation of the AVP code, Name, and vendor ID prohibits a user from overwriting the existing base AVPs.

These AVP actions include the ability to perform the following:

- Routing
- Authentication
- Authorization
- Accounting

Creating an AVP

To create an AVP:

1. From the **Policy Server** section of the navigation pane, select **Custom AVP Definitions**.

The content tree displays the **Custom AVP Definitions** group.

2. Select the **Custom AVP Definitions** group.

The AVP Definition Administration page opens in the work area.

3. Click **Create AVP Definition**.

The New AVP Definition page opens.

4. Enter information as appropriate:

- a. **AVP Name** (required) — The name you assign to the AVP.

The name can only contain the characters A–Z, a–z, 0–9, period (.), hyphen (-), and underline (_). The maximum length is 255 characters.

- b. **Description** — Free-form text that identifies the AVP.

Enter up to 250 characters.

- c. **AVP Code** (required) — A unique numeric value assigned to the new AVP.
- d. **Vendor Id** — Select a vendor from the vendor list.
To add a vendor to the list, see [Managing Custom Vendors](#).
- e. **Protect Flag** (optional) — When checked, specifies the protected AVP values.
- f. **May Encrypt Flag** — The AVP is encrypted if the checkbox is specified.
- g. **Vendor Specific Flag** — The AVP is vendor specific if the checkbox is specified.

 Note:

This box is checked automatically if the value of the vendor ID is not 0.

- h. **AVP Type** (required) — Select the data type from the list:
 - **address**
 - **enumerated**
 - **float32**
 - **float64**
 - **grouped**
 - **id**
 - **int32**
 - **int64**
 - **ipFilterRule**
 - **octetString**
 - **time**
 - **uint32**
 - **uint64**
 - **uri**
 - **utf8String**
- i. **Parent AVP** — If the AVP is a member of a grouped AVP, then the parent AVP must be specified. Select one of the following from the list:
 - **ADC-Rule-Definition:10415**
 - **ADC-Rule-Install:10415**
 - **ADC-Rule-Remove:10415**
 - **ADC-Rule-Report:10415**
 - **AF-Correlation-Information:10415**
 - **Acceptable-Service-Info:10415**
 - **Access-Network-Charging-Identifier-Gx:10415**
 - **Access-Network-Charging-Identifier:10415**
 - **Access-Network-Physical-Access-ID:10415**

- Allocation-Retention-Priority:10415
- Application-Detection-Information:10415
- CC-Money
- Charging-Information:10415
- Charging-Rule-Definition-3GPP2:5535
- Charging-Rule-Definition:10415
- Charging-Rule-Event-Cisco:9
- Charging-Rule-Event-Trigger-Cisco:9
- Charging-Rule-Install-3GPP2:5535
- Charging-Rule-Install:10415
- Charging-Rule-Remove:10415
- Charging-Rule-Report-3GPP2:5535
- Charging-Rule-Report:10415
- Codec-Data-Tmp:10415
- Codec-Data:10415
- Cost-Information
- Default-EPS-Bearer-Qos:10415
- E2E-Sequence
- Envelope:10415
- Event-Report-Indication:10415
- Explicit-Route-Record:21274
- Explicit-Route:21274
- Failed-AVP
- Final-Unit-Indication
- Flow-Description-Info:5535
- Flow-Description:10415
- Flow-Grouping:10415
- Flow-Info:5535
- Flow-Information:10415
- Flow:10415
- G-S-U-Pool-Reference
- Granted-Qos:5535
- Granted-Service-Unit
- Juniper-Discovery-Descriptor:2636
- Juniper-Provisioning-Descriptor:2636
- LI-Indicator-Gx:12951
- LI-TargetMFAddr:12951

- **Media-Component-Description:10415**
- **Media-Sub-Component:10415**
- **Multiple-Services-Credit-Control**
- **Offline-Charging:10415**
- **PCEF-Forwarding-Info:971**
- **PCEF-Info:971**
- **PS-Furnish-Charging-Information:10415**
- **PS-information:10415**
- **Packet-Filter-Information:10415**
- **Qos-Information-3GPP2:5535**
- **Qos-Information:10415**
- **Qos-Rule-Install:10415**
- **Qos-Rule-Definition:10415**
- **Qos-Rule-Remove:10415**
- **Qos-Rule-Report:10415**
- **Reachable-Peer:21274**
- **Redirect-Information:10415**
- **Redirect-Server**
- **Requested-Qos:5535**
- **Requested-Service-Unit**
- **Service-Information:10415**
- **Service-Parameter-Info**
- **Siemens-DL-SDP-Data:4329**
- **Siemens-UL-SDP-Data:4329**
- **Subscription Id**
- **Subscription-Id-3GPP:10415**
- **Supported-Features:10415**
- **TDF-Information:10415**
- **TFT-Packet-Filter-Information:10415**
- **TMO-Redirect-Server-29168**
- **Time-Quota-Mechanism:10415**
- **Trigger:10415**
- **Tunnel-Header-Filter:10415**
- **Unit-Value**
- **Usage-Monitoring-Control:21274**
- **Usage-Monitoring-Information:10415**
- **Used-Service-Unit**

- **User-CSG-Information:10415**
 - **User-Equipment-Info**
 - **User-Location-Info-3GPP:10415**
 - **VZW-Access-Network-Physical-Access-ID:12951**
 - **Vendor-Specific-Application-Id**
 - **Vzw-Trigger:12951**
5. Click **Save**.
 6. If the AVP name matches the name of a standard AVP, a confirmation message displays. Click **OK** to overwrite the existing AVP.

The AVP is created.

Figure 16-1 shows an example of a base AVP definition defined as a custom AVP for use in a non-standard application message.

Figure 16-1 Sample AVP Definition

The screenshot shows the 'AVP Definition Administration' window. On the left, under 'New AVP Definition', is a 'Configuration' section with labels for AVP Name, Description, AVP Code, Vendor Id, Mandatory Flag, Protect Flag, May Encrypt Flag, Vendor Specific Flag, AVP Type, and Parent AVP. On the right, the corresponding values are entered: AVP Name is 'Charging-Characteristics-3GPP', Description is empty, AVP Code is '13', Vendor Id is '3GPP' (selected from a dropdown), Mandatory Flag is unchecked, Protect Flag is unchecked, May Encrypt Flag is checked, Vendor Specific Flag is checked, AVP Type is 'utf8String' (selected from a dropdown), and Parent AVP is 'QoS-Information-3GPP2:5535' (selected from a dropdown). At the bottom left are 'Save' and 'Cancel' buttons.

Modifying an AVP

To modify an AVP:

1. From the **Policy Server** section of the navigation pane, select **Custom AVP Definitions**.

The AVP Definition Administration page opens in the work area, listing the defined AVPs.

2. Select the AVP to modify.

The AVP Definition Administration page opens, displaying information about the AVP.

3. Click **Modify**.

The Modify AVP Definition page opens.

4. Modify AVP information as required.

For a description of the fields contained on this page, see [Creating an AVP](#).

5. Click **Save**.

The AVP is modified.

Deleting an AVP

To delete an AVP:

1. From the **Policy Server** section of the navigation pane, select **Custom AVP Definitions**.

The AVP Definition Administration page opens in the work area, listing the defined AVPs.

2. Delete the AVP using one of the following methods:

- From the work area, click  (trash can icon), located to the right of the AVP.
- From the content tree, select the AVP and click **Delete**.

A confirmation message displays.

3. Click **OK**.

The AVP is deleted.

Managing Custom Vendors

This chapter describes how to create, modify, and delete custom vendor definitions in the CMP system.

Custom vendors are used in RADIUS Change of Authorization (CoA) messages.

About Custom Vendors

A custom vendor is used to define a vendor not stored in a RADIUS dictionary that is part of the CMP database. This dictionary includes vendor IDs and text descriptions, and includes standard vendor-specific attributes (VSAs). You can define custom vendors, define VSAs for them, and add them to the dictionary.

Custom VSAs are typically used in a RADIUS Change of Authorization (CoA) message. You can create policy conditions to evaluate the presence of VSAs in RADIUS messages, and to include custom VSAs in RADIUS response messages.

For information on how to create a VSA, see [Managing Custom VSAs](#). For information on how to use a VSA in a RADIUS CoA message, see [Managing RADIUS CoA Templates](#).

Creating a Custom Vendor

To create a custom vendor:

1. From the **Policy Server** section of the navigation pane, select **Custom Vendors**.
The content tree displays the Custom Vendors group.
2. Select the **Custom Vendors** group.
The Custom Vendor Administration page opens in the work area.
3. Click **Create Custom Vendor**.
The Create Custom Vendor page opens.
4. Enter information as appropriate:
 - a. **Name** (required) — The name you assign to the vendor.
The name can only contain the characters A–Z, a–z, 0–9, period (.), hyphen (-), and underline (_).
 - b. **Description** — Free-form text that identifies the vendor.
Enter up to 250 characters.
 - c. **Vendor Id** — Enter the vendor ID.
Enter a positive integer.
5. Click **Save**.

The custom vendor is defined in the RADIUS dictionary and can now be assigned a vendor-specific attribute (VSA) and used in a policy. See [Managing Custom VSAs](#) for more information about VSAs.

Modifying a Custom Vendor

To modify a custom vendor definition:

1. From the **Policy Server** section of the navigation pane, select **Custom Vendors**.
The Custom Vendor Administration page opens in the work area, listing the defined custom vendors.
2. Select the custom vendor definition you want to modify.
The Custom Vendor Administration page displays information about the vendor.
3. Click **Modify**.
The Modify Custom Vendor page opens.
4. Modify vendor information.
For a description of the fields contained on this page, see [Creating a Custom Vendor](#).
5. Click **Save**.

The custom vendor definition is modified.

Deleting a Custom Vendor

You cannot delete a custom vendor definition that is used in a CoA template.

To delete a custom vendor definition:

1. From the **Policy Server** section of the navigation pane, select **Custom Vendors**.
The Custom Vendor Administration page opens in the work area, listing the defined custom vendors.
2. Delete the custom vendor using one of the following methods:
 - From the work area, click  (trash can icon), located to the right of the vendor.
 - From the content tree, select the vendor and click **Delete**.A confirmation message displays.
3. Click **OK**.

The vendor is removed from the list.

The custom vendor definition is deleted.

Managing Custom VSAs

This chapter describes how to create, modify, and delete custom vendor-specific attributes (VSAs) in the CMP system.

In a wireless network, custom VSAs are used to carry vendor-specific data.

**Note:**

Managing custom VSAs is a function that is applicable to RADIUS CoA mode only.

About Custom VSAs

A vendor-specific attribute (VSA) is used to encapsulate data specific to a vendor device. A VSA consists of a vendor ID and the attribute value. VSAs are stored in a RADIUS dictionary that is part of the CMP database. The dictionary includes a text description of the VSA and type information, and includes standard VSAs. You can define VSAs and add them to the dictionary.

Custom VSAs are typically used in a RADIUS Change of Authorization (CoA) message. You can create policy conditions to evaluate the presence of VSAs in RADIUS messages, and to include custom VSAs in RADIUS response messages.

For information on how to assign values to VSAs, and then send them in a RADIUS CoA message, see [Managing RADIUS CoA Templates](#).

**Note:**

Custom VSAs is a function that is applicable to RADIUS CoA mode only.

Creating a Custom VSA

**Note:**

Custom VSAs is a function that is applicable to RADIUS CoA mode only.

To create a custom VSA:

1. From the **Policy Server** section of the navigation pane, select **Custom VSA Definitions**.
The content tree displays the **Custom VSA Definitions** group.
2. Select the **Custom VSA Definitions** group.

The VSA Definition Administration page opens in the work area.

3. Click **Create VSA Definition**.

The New VSA Definition page opens.

4. Enter information as appropriate:

a. **Name** (required) — The name you assign to the VSA.

The name can only contain the characters A–Z, a–z, 0–9, period (.), hyphen (-), and underline (_).

b. **Description** — Free-form text that identifies the VSA.

Enter up to 250 characters.

c. **VSA Code** (required) — Enter an integer representing the VSA. The default is 0.

d. **Vendor Id** — Select the available vendor from the pulldown list (the vendor is stored and displayed by a vendor ID):

- **IETF** (default)
- **3GPP**
- **3GPP2**
- **Camiant**
- **Cisco**
- **Cisco-BBSM**
- **Cisco-VPN3000**
- **Cisco-VPN5000**
- **Juniper**
- **Juniper-M-Series**
- (Any custom vendors appear at the end of the list. For information about custom vendors, see [Managing Custom Vendors](#).)

e. **VSA Type** (required) — Select the attribute data type from the pulldown list:

- **octets**
- **ipv6prefix**
- **text**
- **ipaddr**
- **abinary**
- **integer**
- **evs**
- **string**
- **ifid**
- **enum**
- **ipv6addr**
- **date**

- **tlv**
 - f. **Compound Type** (required) — Select the description of the attribute structure from the pulldown list:
 - **Map**
 - **Pair**
 - **Single-Value**
 - **List**
 - g. **Field Separator** — If the attribute value has multiple fields, enter the field separator.
 - h. **Sub-Field Separator** — If the attribute value has sub-fields, enter the sub-field separator.
5. Click **Save**.

The custom VSA is created. The VSA definition displays on the VSA Definition Administration page and is defined in the RADIUS dictionary. The custom VSA can be assigned a value. For more information, see [Managing RADIUS CoA Templates](#).

Modifying a Custom VSA

To modify a custom VSA:

1. From the **Policy Server** section of the navigation pane, select **Custom VSA Definitions**.
The VSA Definition Administration page opens in the work area, listing the defined VSAs.
2. Select the VSA to modify.
The VSA Definition Administration page displays information about the VSA.
3. Click **Modify**.
The Modify VSA Definition page opens.
4. Modify VSA information.
For a description of the fields contained on this page, see [Creating a Custom VSA](#).
5. Click **Save**.

The VSA definition is modified.

Deleting a Custom VSA

You cannot delete a VSA that is used in a CoA template.

To delete a custom VSA:

1. From the **Policy Server** section of the navigation pane, select **Custom VSA Definitions**.
The VSA Definition Administration page opens in the work area, listing the defined monitoring keys.
2. Delete the VSA using one of the following methods:
 - From the work area, click  (trash can icon), located to the right of the VSA.
 - From the content tree, select the VSA and click **Delete**.

A confirmation message displays.

3. Click **OK**.

The VSA is deleted.

Managing Match Lists

This chapter describes how to create and manage match lists in the CMP system.

In a wireless network, a match list is a set of defined values that can represent, for example, IDs or Internet addresses. Match lists provide whitelist and blacklist functions in policy rules. Match lists support wildcard matching.

About Match Lists

A match list is a set of values in various categories, including access point names (APNs), subscriber IMSIs, location area codes (LACs), service area codes (SACs), Internet addresses, and user equipment identities. A match list can function as a whitelist (listing items to be included) or a blacklist (listing items to be excluded). By using a match list, you can, for example, apply a policy to all subscribers in a set of LACs, or block access to a list of Internet addresses known to be high risk.

Match lists support wildcards. Using wildcards, a range of values can be specified compactly.

Creating a Match List

To create a match list:

1. From the **Policy Server** section of the navigation pane, select **Match Lists**.
The content tree displays the **Match Lists** group.
2. Select the **Match Lists** group.
The Match List Administration page opens in the work area.
3. Click **Create Match List**.
The New Match List page opens.
4. Enter the following information:
 - a. **Name** — The name assigned to the match list.
The name can only contain the characters A–Z, a–z, 0–9, period (.), hyphen (-), and underline (_). The maximum length is 40 characters.
 - b. **Description/Location** — Free-form text.
 - c. **Type** — Select from the following:
 - **string** (default) — The list consists of strings.
 - **wildcard string** — The list consists of wildcard match patterns that use an asterisk (*) to match zero or more characters or a question mark (?) to match exactly one character.
 - **IPv4 address** — The list consists of IP addresses in IPv4 format.
 - **IPv6 address** — The list consists of IP addresses in IPv6 format.

- **MCC-MNC** — The list consists of Mobile Country Code-Mobile Network Code pairs.
 - **Location Info** — The list consists of locations (formatted as string, wildcard string, or numeric range) and time periods selected from the time periods list. Time period is optional and the default value is none. For information about creating and managing time periods, see [Managing Policy Time Periods](#).
- d. **Items** — Type an entry and click **Add**; to remove one or more entries from the list, select them and click **Delete**.

The following match types are available:

- **APN** (access point name)
- **User Equipment Identity**
- **USER IMSI**
- **USER E.164**
- **USER SIP URI**
- **USER NAI**
- **Serving MCC-MNC**
- **Cell Identifier**
- **Location Area Code**
- **Service Area Code**
- **Routing Area Code**
- **Routing Area Identifier**
- **Tracking Area Code**
- **E-UTRAN Cell Identifier**

You can enter a match string combining multiple types (for example, a Location Area Code and a Service Area Code) by separating the types with commas (,); for example, *lac1, sac1*. If you define multiple-type match lists, the types must be in the order shown.

5. Click **Save**.

The match list is defined in the CMP database and can now be used in a policy.

Modifying a Match List

To modify a match list:

1. From the navigation pane, select **Match Lists**.
The content tree displays the **Match Lists** group.
2. From the content tree, select the **Match Lists** group.
The Match List Administration page opens, displaying the list of defined match lists.
3. Select the match list you want to modify.
Match list information is displayed.

4. Click **Modify**.

The Modify Match List page opens.

5. Modify match list information as required.

You cannot change the type.

6. Click **Save**.

The match list is modified.



Note:

You can also use the OSSI XML Interface to import and export match lists. This facilitates bulk changes or record keeping. For more information, see the *OSSI XML Interface Definitions Reference Guide*.

Deleting a Match List

To delete a match list:

1. From the **Policy Server** section of the navigation pane, select **Match Lists**.

The content tree displays the **Match Lists** group.

2. From the content tree, select the **Match Lists** group.

The Match List Administration page opens, displaying the list of defined match lists.

3. Delete the match list using one of the following methods:

- From the work area, click  (trash can icon), located to the right of the match list.
- From the content tree, select the match list and click **Delete**.

A confirmation message displays.

4. Click **OK**.

The match list is deleted.

Managing Media Profiles

This chapter defines how to manage media profiles in the CMP system.

In a cable network, a media profile describes a CODEC supported for Rx-to-PCMM translation.

**Note:**

Media Profiles is a function that is applicable to Cable mode only.

About Media Profiles

**Note:**

Media Profiles is a function that is applicable to Cable mode only.

A media profile describes a CODEC supported for Rx-to-PCMM translation. The MPE device includes a predefined set of media profiles, and you can create new RTP (real-time transport protocol) profiles. After you have defined a media profile in the CMP system, it is automatically deployed to MPE devices.

Media profiles are named *codec_name-transport_type-sample_rate*. Media profiles are mapped to CODECs based on the information received in a session description protocol (SDP) message.

In defining a media profile in the CMP system, you specify its name, transport type, sample rate, frame size (in both milliseconds and bytes), and packetization time.

**Note:**

You cannot create media profiles for the UDPTL or UDP transport types.

[Predefined Media Profiles](#) describes the predefined media profiles.

Predefined Media Profiles

The CMP installs a set of Media Profiles. The following tables lists the Predefined media files available.

Table 20-1 Predefined Media Profiles

CODEC Name	AVT Profile	Frame Length (ms)	Frame Size (bytes)	Bit Rate (kbps)	Sample Rate (kHz)
PCMU	0	0.125	1	64	8
G721	2	0.125	1	64	8
GSM	3	20	33	13.2	8
G723	4	30	24	5.3, 6.3	8
PCMA	8	0.125	1	64	8
G722	9	0.125	1	64	8
G722-48	dynamic	1	6	48	8
G722-56	dynamic	1	7	56	8
G722-64	dynamic	1	8	64	8
G728	15	2.5	5	16	8
G729	18	10	10	8	8
G726-16	dynamic	0.5	1	16	8
G726-24	dynamic	1	3	24	8
G726-32	dynamic	0.25	1	32	8
G726-40	dynamic	1	5	40	8
G729D	dynamic	10	8	6.4	8
G729E	dynamic	10	15	11.8	8
GSM-EFR	dynamic	20	31	12.2	8
iLBC	dynamic	20	38	13.33	8
iLBC	dynamic	30	50	15.2	8
BV16	dynamic	5	10	16	8
BV32	dynamic	5	20	32	16
RED	dynamic	10	160	128	8
VMR-WB	dynamic	20	34	13.6	8
SMV0	dynamic	20	22	8.8	8
evrc0	dynamic	20	22		8
evrcb0	dynamic	20	22		8
evrcwb0	dynamic	20	22		8
evrcwb0	dynamic	20	22		16
amr	dynamic	20	32		8
AMR/8000	dynamic	20	14	4.75	8
AMR/8000	dynamic	20	15	5.15	8
AMR/8000	dynamic	20	16	5.9	8
AMR/8000	dynamic	20	18	6.7	8
AMR/8000	dynamic	20	20	7.4	8
AMR/8000	dynamic	20	22	7.95	8
AMR/8000	dynamic	20	27	10.2	8
AMR/8000	dynamic	20	32	12.2	8
amr-wb	dynamic	20	61		16
amr-wb/ 16000	dynamic	20	18		16

Table 20-1 (Cont.) Predefined Media Profiles

CODEC Name	AVT Profile	Frame Length (ms)	Frame Size (bytes)	Bit Rate (kbps)	Sample Rate (kHz)
amr-wb/16000	dynamic	20	24		16
amr-wb/16000	dynamic	20	33		16
amr-wb/16000	dynamic	20	37		16
amr-wb/16000	dynamic	20	41		16
amr-wb/16000	dynamic	20	47		16
amr-wb/16000	dynamic	20	51		16
amr-wb/16000	dynamic	20	59		16
amr-wb/16000	dynamic	20	61		16

Creating a Media Profile



Note:

Media Profiles is a function that is applicable to Cable mode only.

To create a media profile:

1. From the **Policy Server** section of the navigation pane, select **Media Profiles**.
The content tree displays the **Media Profiles** group.
2. Select the **Media Profiles** group.
The Media Profile Administration page opens in the work area, listing available media profiles.
3. Click **Create Media Profile**.
The New Media Profile page opens.
4. Enter the following information:
 - a. **Codec Name** — Unique media subtype assigned to the media profile.
This is defined in the IANA MIME registration for the CODEC. Enter a string of up to 255 characters.
 - b. **Transport Type** — Select from the following:
 - **RTP/AVP** (default) — RTP audio-video profile.
 - **RTP/SAVP** — RTP secure audio-video profile.

- **RTP/AVPF** — RTP extended audio-video profile with feedback.
- c. **Payload Number** — The payload number.
Valid payload numbers range from 0 through 127. Enter -1 to indicate an unknown payload number.

 Note:

You cannot add a CODEC that is predefined with a payload number in the range of 0 to 96.

- d. **Sample Rate (kHz)** — The sampling rate of the CODEC in KHz.
The valid range is an integer from 1 through 100 KHz.
- e. **Frame Size in Milliseconds** — The size of one audio frame in milliseconds.
This is the length of time represented by one audio frame. A single RTP packet may contain multiple audio frames. The bitrate is calculated using the frame size in milliseconds, the frame size in bytes, and the packetization time. The valid range is 0 through 100 ms.
- f. **Frame Size in Bytes** — The size of one audio frame size in bytes.
This is the size represented by one audio frame. A single RTP packet may contain multiple audio frames. The bitrate is calculated using the frame size in milliseconds, the frame size in bytes, and the packetization time. The valid range is 1 through 1,500 bytes.
- g. **Packetization Time** — The length of time, in milliseconds, represented by the media in a packet.
The bitrate is calculated using the frame size in milliseconds, the frame size in bytes, and the packetization time. The valid range is 1 through 100.
- h. **Always Use Default Ptime** — Select to always use the default packetization time, ignoring the value received in the SDP message.
The default is unchecked.

5. Click **Save**.

The media profile is created.

Modifying a Media Profile

To modify a media profile:

1. From the **Policy Server** section of the navigation pane, select **Media Profiles**.
The content tree opens.
2. From the content tree, select the **Media Profiles** group.
The Media Profile Administration page opens, displaying the list of defined media profiles.
3. Select the media profile you want to modify.
The profile information for the media displays.
4. Click **Modify**.

The Modify Media Profile page opens.

5. Modify media profile information.

For a description of the fields contained on this page, see [Creating a Media Profile](#).

6. Click **Save**.

The media profile is modified.

Deleting a Media Profile

To delete a media profile:

1. From the **Policy Server** section of the navigation pane, select **Media Profiles**.

The content tree opens.

2. From the content tree, select the **Media Profiles** group.

The Media Profile Administration page opens, displaying the list of defined media profiles.

3. Delete the media profile using one of the following methods:

- From the work area, click  (trash can icon) located to the right of the media profile.
- From the content tree, select the media profile and click **Delete**.

A confirmation message displays.

4. Click **OK**.

The media profile is deleted.

Managing Monitoring Keys

This chapter describes how to create and manage monitoring keys in the CMP system.

In a wireless network, a monitoring key associates quota profiles with policy and charging control (PCC) and application detection control (ADC) rules for usage tracking.

**Note:**

The actual options you see depend on whether or not your CMP system is configured in wireless Gx mode, wireless Gy mode, or both.

About Monitoring Keys

A monitoring key is a unique string that identifies the quota profile to be used by a policy and charging control (PCC) rule and application detection control (ADC) rule for usage tracking. The monitoring key is associated with the quota profile by selecting a policy action that grants usage to a selected number of quota profiles. You configure monitoring keys through the CMP system.

The PCC Rule Profile is used to populate the Charging Rule Definition attribute-value pair (AVP) and the ADC Rule definition AVP values in a Diameter message when a new rule is installed. Therefore, the monitoring key to be defined in the PCC Rule Profile is specified in the Monitoring Key AVP, which is contained in the Charging Rule Definition or ADC Rule Definition AVP for that particular rule. The monitoring key is supported for Sd messages, and is compatible with both Release 9 and previous releases. When reporting usage to the MPE device, the monitoring key associated with the PCC/ADC Rule is included in a Usage Monitoring AVP, along with the usage accumulated. The usage accumulated is reported for the total volume, uplink volume, or downlink volume.

At the session level, the monitoring key is optional, but is set by the selection of the policy action. These policy actions include the ability to:

- Disable or re-enable usage tracking for specified monitoring keys
- Request a usage report from the PCEF for specified monitoring keys
- Monitor multiple PCC/ADC rules against the same quota
- Monitor usage for a PCC/ADC rule or session level against multiple quotas such as monthly and daily quotas

**Note:**

The granted usage sent to the PCEF/TDF will always be the smallest remaining amount of the quotas, and the re-validation time will always be calculated based on the shortest or closest time in the future for the quotas.

- Change a monitoring key for a rule or session level during the middle of a session upon receiving a Credit Control Request (CCR) update message

Creating a Monitoring Key

To create a monitoring key, perform the following steps:

1. From the **Policy Server** section of the navigation pane, select **Monitoring Key**.

The content tree displays the Monitoring Key group.

2. Select the **Monitoring Key** group.

The Monitoring Key Administration page opens in the work area.

3. Click **Create Monitoring Key**.

The New Monitoring Key page opens.

4. Enter information for the monitoring key:

- a. **Name** (required) — The name you assign to the monitoring key.

The name can only contain the characters A–Z, a–z, 0–9, period (.), hyphen (-), and underline (_). The maximum length is 255 characters.

- b. **Description** — Free-form text that identifies the monitoring key.

Enter up to 250 characters.

- c. **Type** (required) — The level assigned to the monitoring key.

Select **PCC_RULE_LEVEL** value (1), **ADC_RULE_LEVEL** value (2), or **SESSION_LEVEL** from the list.

- d. **Key** — Specifies unique string from all other monitoring keys.

The key can be up to 255 characters long and must not contain backslashes (\), quotation marks ("), semicolons (;), commas (,), or apostrophes (').

5. Click **Save**.

The monitoring key displays on the Monitoring Key Administration page. After you define monitoring keys, you can:

- Select them from the PCC Rule Profile when configuring quota profiles
- Use them in policy actions in the Policy Wizard

Modifying a Monitoring Key

To modify a monitoring key:

1. From the **Policy Server** section of the navigation pane, select **Monitoring Key**.

The Monitoring Key Administration page opens in the work area, listing the defined monitoring keys.

2. Select the monitoring key you want to modify.

The Monitoring Key Administration page displays information about the monitoring key.

3. Click **Modify**.

The Modify Monitoring Key page opens.

4. Modify the monitoring key.

For a description of the fields contained on this page, see [Creating a Monitoring Key](#).

5. Click **Save**.

The monitoring key definition is modified.

Deleting a Monitoring Key

To delete a monitoring key:

1. From the **Policy Server** section of the navigation pane, select **Monitoring Key**.

The Monitoring Key Administration page opens in the work area, listing the defined monitoring keys.

2. Delete the monitoring key using one of the following methods:

- From the work area, click  (trash can icon), located to the right of the monitoring key.
- From the content tree, select the monitoring key and click **Delete**.

A confirmation message displays.

3. Click **OK**.

The monitoring key is deleted.

Managing Notification Servers

This chapter describes how to create and manage notification servers in the CMP system.

In a wireless network, a notification server controls event notifications driven by policy actions.

About Notification Servers

A notification server processes event notifications in response to policy actions for HTTP request messages. You configure notification servers through the CMP system with SMPP/XML mode enabled.

A notification server can be associated with one or more MPE devices.

At the session level, the notification server is optional, but is set by the selection of the policy action. These policy actions include the ability to:

- Send notifications using a dynamic URL
- Send notifications using a static URL

The audit log records all notification server actions (create, modify, and delete), policy creation and modification, and associations (policy server and configuration template).

Creating a Notification Server

To create a notification server, the CMP system must have the SMPP/XML mode enabled. To create a notification server:

1. From the **Policy Server** section of the navigation pane, select **Notification Servers**.

The content tree displays the **Notification Servers** group.

2. Select the **Notification Servers** group.

The Notification Server Administration page opens in the work area.

3. Click **Create Notification Server**.

The New Notification Server page opens.

4. Enter the **Name** (required) for the notification server.

When you configure policies using notification servers, you will use this name. The name can only contain the characters A–Z, a–z, 0–9, period (.), hyphen (-), and underline (_). The maximum length is 40 characters.

5. Enter a **Description / Location** (optional).

The description is free-form text containing up to 255 characters.

6. Enter the **Destination URL** (required).

Use the FQDN or the IP address in either IPv4 or IPv6 format (for example, *http://10.15.20.190:80*). This parameter can contain up to 255 characters and must be unique. The SMSR creates a persistent connection to this end point.

7. Enter the **Connection Pool [1-5]**.

Identifies the number of persistent connections to this end point (default is 1).

8. **Keep Alive Interval (seconds)**.

Indicates the number of seconds to keep the persistent connection active. The valid range is 0 to 300 seconds. The default is 30.

9. In the **Policy Servers associated with this Notification Server** section, do one of the following:

- Select **ALL** to associate the notification server with all MPE devices.
- Select individual MPE devices.
- Do not select any MPE devices.

10. Click **Save**.

The notification server is created.

After you create a notification server, you can associate it with MPE devices and use it in policy actions in the policy wizard.

Enabling Notification on an MPE device

To enable notification on an MPE device:

1. From the **Policy Server** section of the navigation pane, select **Configuration**.
The content tree displays the **Policy Servers** group.
 2. Select the policy server for notification.
The Policy Server Administration page opens in the work area.
 3. Click **Modify**.
The Modify Policy Server page appears.
 4. In the **Generic Notification Configuration** section, select **Notification Enabled**.
 5. Click **Save**.
The updated Policy Server page appears.
- The CMP system updates the policy server's configuration to enable notification.

Viewing a Notification Server

To view a notification server:

1. From the **Policy Server** section of the navigation pane, select **Notification Servers**.
The content tree displays the **Notification Servers** group.
2. Select the **Notification Servers** group.

The Notification Server Administration page opens in the work area and lists all the notification servers.

3. Select the notification server you want to view.

The Notification Server page appears showing the current configuration for the selected server.

4. From this page:

- Click **Modify** to change the server configuration.
- Click **Delete** to remove the server from the system.

Modifying a Notification Server

To modify a notification server:

1. From the **Policy Server** section of the navigation pane, select **Notification Servers**.

The content tree displays the **Notification Servers** group.

2. Select the **Notification Servers** group.

The Notification Server Administration page opens in the work area and lists all the notification servers.

3. Select the notification server you want to change.

The Notification Server page appears showing the current configuration for the selected server.

4. Click **Modify**.

The Modify Notification Server page appears.

5. Edit the configuration settings as needed.

Note:

If you modify the notification server name and the server is associated with a policy, then the policy is redeployed with the modified name and the following message is displayed: This notification server name has changed. The following policies have been re-deployed: *Policy Name (s)*

The changed notification server configuration is sent to the associated policy servers.

6. Click **Save**.

The updated Notification Server page appears.

The notification server configuration is updated and the any associated policies are redeployed.

Associating a Notification Server with an MPE device

To associate a notification server with an MPE device:

1. From the **Policy Server** section of the navigation pane, select **Configuration**.
The content tree displays the **Policy Servers** group.
 2. From the listing of policy servers, select the specific MPE device.
The Policy Server Administration page appears.
 3. Select the **Policy Server** tab.
The Policy Server page for the selected device appears.
 4. Click **Modify**.
The Policy Server page becomes editable.
 5. In the section for **Notification Servers**, click **Manage**.
A window displays listing the **Available** notification servers and the **Selected** servers.
 6. From the **Available** servers list, select the notification server with which to associate the MPE device.
 7. Click --> (right arrow icon).
The selected notification server is added to the **Selected** listing.
 8. Click **OK**.
 9. Click **Save**.
- The association of the MPE device with the notification server is created. If you remove a notification server, the association disappears from the **Notification Servers** listing.

Associating a Notification Server with a Configuration Template

To associate a notification server with a configuration template:

1. From the **Policy Server** section of the navigation pane, select **Configuration Template**.
The content tree displays the **Templates** group.
2. From the listing of templates, select the specific **Configuration Template**.
The Configuration Template Administration page appears.
3. Select the **Policy Server** tab.
The Policy Server page for the selected template appears.
4. Click **Modify**.
The Modify Policy Server page becomes editable.
5. In the section for **Notification Servers**, click **Manage**.
A window appears listing the **Available** notification servers and the **Selected** servers.
6. From the **Available** servers list, select the notification server with which to associate the .

7. Click  (right arrow icon).

The selected notification server is added to the **Selected** listing.

8. Click **OK**.

9. Click **Save**.

The association of the configuration template with the notification server is created. If you remove a notification server, the association disappears from the **Notification Servers** listing.

Removing the Notification Server Association with an MPE device

To remove an association of a notification server with an MPE device:

1. From the **Policy Server** section of the navigation pane, select **Configuration**.

The content tree displays the **Policy Servers** group.

2. From the listing of policy servers, select the specific MPE device.

3. Select the **Policy Server** tab.

The Policy Server page for the selected device appears.

4. Click **Modify**.

The Policy Server page becomes editable.

5. In the section for **Notification Servers**, click **Manage**.

A list displays the **Available** notification servers and the **Selected** servers.

6. In the **Selected** servers list, select the notification server to remove.

7. Click  (left arrow icon).

The selected notification server is removed from the **Selected** listing and appears in the **Available** listing.

8. Click **OK**.

9. Click **Save**.

The association of the MPE device with the notification server is removed. If you specified a new notification server, the new association appears in the **Notification Servers** listing.

Deleting a Notification Server



Note:

You can only delete a notification server that is not associated with any of the following:

- Policy
- Policy table
- Policy server (MPE device)
- Policy server configuration template

See [Removing the Notification Server Association with an MPE device](#) for details on removing an association with an MPE device. See [Modifying a Policy Rule](#) for details on modifying policies.

To delete a notification server:

1. From the **Policy Server** section of the navigation pane, select **Notification Servers**.
The content tree displays the **Notification Servers** group.
2. Select the **Notification Servers** group.
The Notification Server Administration page opens in the work area.
3. Delete the server using either of the following methods:
 - From the work area, click the **Delete** icon located to the right of the notification server.
 - From the content pane, select the notification server and click **Delete**.A message appears asking you to confirm the deletion.
4. Click **OK**.

The notification server is removed from the Notification Server Administration page.

Managing Policy Counter Identifiers

This chapter describes how to create and manage policy counter IDs in the CMP system.

In a wireless network, a policy counter ID defines the name, optional description, and default online charging server (OCS) value for which status can be received from the OCS server. Policy counter IDs are used in policies, and grouped together here for ease of management.

About Policy Counter IDs

A policy counter ID defines the name, optional description, and default online charging server (OCS) value for which status can be received from the OCS server. After a policy counter ID is defined, you can use policy counter IDs in policies.

In the Sy reference point, an OCS acts as the server and the MPE device acts as the client. For a subscriber, the MPE device requests status from the OCS for a set of policy counter IDs. If the request is successful, the OCS returns the status information for the subscriber to the MPE device and an Sy session is created for the subscriber. The OCS automatically sets up a subscription for the requested policy counter IDs and then notifies the MPE device of any changes to those values.

The Sy protocol provides for four types of messages between the MPE device and the OCS:

1. For the MPE device to request status for an initial set of policy counter IDs and subscribe for notifications for those policy counter IDs
2. For the MPE device to request an update status and possibly update the policy counter ID subscription
3. For the OCS to notify the MPE device of a status change for a set of policy counter IDs for a subscriber
4. For the MPE device to end the Sy session with the OCS, cancelling all subscriptions associated with that session

You can define policy counter IDs in the CMP database and then refer to them in policies.

Creating a Policy Counter ID

To create a policy counter ID:

1. From the **Policy Server** section of the navigation pane, select **Policy Counter ID**.
The content tree displays the **Policy Counter ID** group. The default group is **ALL**.
2. Select the **Policy Counter ID** group.
The Policy Counter ID Administration page opens in the work area.
3. Click **Create Policy Counter ID**.
The New Policy Counter ID page opens.
4. Enter the **Name** (required).

The name assigned to the Policy Counter ID. This is the name you use in policies. The name can be up to 255 characters long and must not contain quotation marks (") or commas (,).

5. Enter the **Identifier** (required).

Free-form text. This is the key between the MPE device and the OCS.

6. Enter a **Description**

Free-form text.

7. Enter the **Default Status**.

Free-form text. The default status for this policy counter ID.

8. Click **Save**.

The policy counter ID is defined in the CMP database and can be used in a policy.

Modifying a Policy Counter ID

To modify a policy counter ID:

1. From the navigation pane, select **Policy Counter ID**.

The content tree displays the **Policy Counter ID** group.

2. From the content tree, select the **Policy Counter ID** group.

The Policy Counter ID Administration page opens, displaying the list of defined Policy Counter IDs.

3. Select the Policy Counter ID you want to modify.

Policy Counter ID information is displayed.

4. Click **Modify**.

The Policy Counter ID List page opens.

5. Modify Policy Counter ID information as required.

6. Click **Save**.

The Policy Counter ID is modified.



Note:

You can also use the OSSI XML Interface to import and export match lists. This facilitates bulk changes or record keeping. For more information, see the *OSSI XML Interface Definitions Reference Guide*.

Deleting a Policy Counter ID

You cannot delete a policy counter ID that is being used in a deployed policy condition.

To delete a policy counter ID:

1. From the **Policy Server** section of the navigation pane, select **Policy Counter ID**.

The content tree displays the **Policy Counter ID** group.

2. From the content tree, select the **Policy Counter IDs** group.
The Policy Counter ID Administration page opens, displaying the list of defined policy counter IDs.
3. Delete the policy counter ID using one of the following methods:
 - From the work area, click  (trash can icon), located to the right of the policy counter ID.
 - From the content tree, select the policy counter ID and click **Delete**.A confirmation message displays.
4. Click **OK**.
The policy counter ID is deleted.

Policy Counter ID Groups

For organizational purposes, you can aggregate policy counter IDs into groups. After a policy counter ID group is created, it can be populated with individual policy counter IDs. The following subsections describe how to manage policy counter ID groups.

Creating a Policy Counter ID Group

To create a policy counter ID group:

1. From the **Policy Server** section of the navigation pane, select **Policy Counter ID**.
The content tree displays a list of Policy Counter ID groups; the initial group is **ALL**.
2. From the content tree, select the **ALL** group.
The Policy Counter ID Administration page opens in the work area, listing all defined policy counter IDs.
3. Click **Create Group**.
The Create Group page opens.
4. Enter the **Name** of the Policy Counter ID group.
The name can only contain the characters A–Z, a–z, 0–9, period (.), hyphen (-), and underline (_). The maximum length is 250 characters.
5. (Optional) Enter a **Description** of the Policy Counter ID group.
6. Click **Save**.
The Policy Counter ID group is created.

Adding a Policy Counter ID to a Policy Counter ID Group

To add a policy counter ID to a policy counter ID group:

1. From the **Policy Server** section of the navigation pane, select **Policy Counter ID**.
The content tree displays a list of policy counter ID groups; the initial group is **ALL**.
2. From the content tree, select the policy counter ID group.
The Policy Counter ID Administration page opens in the work area, displaying the contents of the selected policy counter ID group.

3. Click **Add Policy Counter ID**.

The Add Policy Counter ID page opens, displaying the policy counter IDs not already part of the group.

4. Select the policy counter ID you to add. Use the Ctrl or Shift keys to select multiple policy counter IDs.
5. Click **Save**.

The policy counter ID is added to the policy counter ID group.

Modifying a Policy Counter ID Group

To modify a policy counter ID group:

1. From the **Policy Server** section of the navigation pane, select **Policy Counter ID**.
The content tree displays a list of policy counter IDs; the initial group is **ALL**.
2. From the content tree, select the policy counter ID group you want to modify.
The Policy Counter ID Administration page opens in the work area.
3. Click **Modify**.
The Modify Group page opens.
4. Edit the information.
5. Click **Save**.

The group is modified.

Deleting a Policy Counter ID from a Policy Counter ID Group

Deleting a policy counter ID from a policy counter ID group does not delete the ID. To delete a policy counter ID, see [Deleting a Policy Counter ID](#).

To delete a policy counter ID from a policy counter ID group:

1. From the **Policy Server** section of the navigation pane, select **Policy Counter ID**.
The content tree displays the list of policy counter ID groups.
2. From the content tree, select the policy counter ID group.
The Policy Counter ID Administration page opens in the work area, displaying the contents of the selected policy counter ID group.
3. Click  (scissors icon), located to the right of the policy counter ID.
4. Click **Save**.

The policy counter ID is deleted from the group.

Deleting a Policy Counter ID Group

Deleting a policy counter ID group does not delete any policy counter IDs that are associated with the group. Profiles remain in the ALL group. You cannot delete the ALL group.

To delete a policy counter ID group:

1. From the **Policy Server** section of the navigation pane, select **Policy Counter ID**.

The content tree displays the list of policy counter ID groups.

2. From the content tree, select the policy counter ID group.

The Policy Counter ID Administration page opens in the work area, displaying the contents of the policy counter ID group.

3. Click **Delete**.

A confirmation message displays.

4. Click **OK** to delete the group.

The policy counter ID group is deleted.

Managing Policy Time Periods

This chapter describes how to create and manage time periods in the CMP system.

In a wireless network, a policy time period is used in policy time-of-day conditions.

**Note:**

Certain functions of policy time periods are not applicable to all releases including the following options:

- Different days of a month
- Specific day and time in a specific year

About Policy Time Periods

You can define a library of time periods to specify in policy time-of-day conditions and associate the time periods with multiple policies. Each time period can have one or more times slots defined. A time slot can be:

- Specific time of day.
- Different days of the week.
- Different days of a month.
- Specific years.
- Specific day and time in a specific year.
- Specific day and time in every year.

For example a single time period can have following time slots defined:

- Every Monday at 2 o'clock
- On the last day of the month
- On every Valentines day
- On May 17, 2016
- The first three days of March, July, and September

Creating a Time Period

**Note:**

Certain functions of policy time periods are not applicable to all releases including the following options:

- Different days of a month
- Specific day and time in a specific year

To create a time period:

1. From the **Policy Server** section of the navigation pane, select **Time Periods**.
The content tree displays the **Time Period Administration** group.
2. From the content tree, select the **Time Period Administration** group.
The Time Period Administration page opens in the work area.
3. Click **Create Time Period**.
The New Time Period page opens.
4. To configure the general information for the time period, enter the following:
 - a. **Name** (required) — Name of the time period.
The name can only contain the characters A–Z, a–z, 0–9, period (.), hyphen (-), and underline (_).
 - b. **Description / Location** — A descriptive phrase.
 - c. **Precedence** (required) — A positive integer.
The lower the number, the higher the precedence. If time periods overlap, the time period with the highest precedence (lowest number) applies.
5. To configure time slots table, use the following table functions:

**Note:**

Certain functions of managing policy time periods are not applicable to all releases including the following options:

- Different days of a month
- Specific day and time in a specific year

- **To add a time slot to the table** — Click **Add**; the Add Time Slot window opens. Configure the values as appropriate.

 Note:

Start Time and **End Time** are required. All other values are optional.

- a. **Years** — Click **Please Select Years** and select one or more years.
- b. **Months of Year** — Select one or more months.
- c. **Days of Month** — Click **Please Select Days** and Select one or more days of the month and the direction. To count the days in reverse order (from the last day of the month to the first), select **Reverse**.
- d. **Days of Week**—Select one or more week-day.
- e. **Start Time**—Select the starting time.
- f. **End Time**—Select the ending time.

 Note:

Time slots cannot overlap. If time slots overlap, a message displays and the slots are not saved. See [Figure 24-1](#) for an example of overlapping time slots.

Figure 24-1 Example of Time Slot Overlap

Years	Months	Days	Week-Days	Start Time	End Time
*	Jul,Oct	-1,-2,-3,-4	Mon,Tue,Wed,Thu,Fri	09:40	10:55
2014	*	*	*	10:30	11:45
2014	Feb,Mar	1,2	*	10:30	11:45

[Table 24-1](#) shows how to configure time slots for some example situations.

Table 24-1 Example of Time Slot Definitions

Time Slot	Year	Month	Day
Every Valentines Day	null	Feb	14
January 10th 2016 only	2016	Jan	10
The first five days in every month for the first half of the year	null	Jan, Feb, Mar, Apr, May, Jun	1, 2, 3, 4, 5
The last five days in every month for the second half of 2015 and 2016	2015, 2016	Jul, Aug, Sep, Oct, Nov, Dec	Select Reverse and 1, 2, 3, 4, 5

- **To clone an attribute in the table**—Select an existing attribute in the table and click **Clone**; the Clone window opens with the information for the attribute. Make changes as required.

- **To edit an attribute in the table**—Select the attribute in the table and click **Edit**; the Edit Response window opens, displaying the information for the attribute. Make changes as required.
- **To delete an attribute from the table**—Select the attribute in the table and click **Delete**. A confirmation message displays. Click **Delete** to remove the attribute.

6. Click **Save**.

The time period is defined in the CMP database and can be used in a policy time condition.

Modifying a Time Period

To modify a time period:

1. From the **Policy Server** section of the navigation pane, select **Time Periods**.
The content tree displays the **Time Period Administration** group.
2. From the content tree, select the **Time Period Administration** group.
The Time Period Administration page opens in the work area.
3. Select a time period.
The Time Period Administration page opens.
4. Click **Modify**.
The fields become editable.
5. Modify Time Period information.
For information about the fields, see [Creating a Time Period](#).
6. Click **Save**.
 - Click **Save**.

The time period is defined in the CMP database and can now be used in a policy time condition.

Deleting a Time Period

To delete a time period:

1. From the **Policy Server** section of the navigation pane, select **Time Periods**.
The content tree displays the **Time Period Administration** group.
2. From the content tree, select the **Time Period Administration** group.
The Time Period Administration page opens in the work area.
3. Select the time period using one of the following methods:
 - From the work area, click  (trash can icon), located to the right of the time period.
 - From the content tree, select the time period and click **Delete**.A confirmation message displays.

4. Click **OK**.

The time period is deleted.

About Time-of-Day Triggers

Time-of-day triggers are supported for Diameter Gx sessions. If time-of-day triggers are configured, the MPE device periodically examines policies and provisions the policies to enforcement points, even for connected subscribers.

For example, if a subscriber connects to a network during an off-peak period and continues to use the network into a peak period, the MPE device removes the off-peak policy rule at the enforcement point at the set time and installs the peak policy rule.

The MPE device evaluates policies every 15 minutes, that is on the hour, 15 minutes past the hour, 30 minutes past the hour, and 45 minutes past the hour. If a time period is changed, it can take up to 15 minutes for the change to take effect.



Note:

If a time period transition occurs and an MPE device is still updating sessions for the previous period, the MPE device ends the updates in progress and processes the new transition by updating the sessions based on the time periods for the new time period.

Time-of-day triggering must be enabled as part of MPE configuration. For more information, see the appropriate *CMP User's Guide*.

Managing Presence Reporting Area Lists

This chapter describes how to create and manage Presence Reporting Area (PRA) lists in the CMP system.

In a wireless network, PRA lists are used to apply policies to users within or outside specific areas.

**Note:**

Managing PRA lists is a function that is applicable to 3GPP mode only.

About Presence Reporting Area Lists

A PRA list is a list of areas in which user equipment presence is reported to the PCRF. PRA lists are used to create location-specific policies that are triggered and applied whenever the user equipment either enters or leaves a PRA. PRA list areas can be designated with various types of value, including tracking area identities (TAI), routing area identities (RAI), Macro eNodeB, Home eNodeB, E-UTRAN cell global identities (ECGI), service area identities (SAI), and cell global identities (CGI).

You can create two types of PRA list: Core Network pre-configured and UE-dedicated. A Core Network pre-configured PRA list is defined on the MME/SSGN side and is used by the CMP in policies. Core Network pre-configured PRA lists are used to create area-specific policies that apply to all or many subscribers on a network. A UE-dedicated PRA list is defined either in the CMP or in subscriber profiles. UE-dedicated PRA lists are used to create area-specific policies that apply to small groups of subscribers on a network.

Presence Reporting Area List Case Study

The following case study demonstrates how PRA lists can be used with policies on a wireless network.

A wireless carrier, Example Inc., uses PRA lists to apply policies to user equipment within specific areas. Example Inc. implements PRA lists in three scenarios: managing QoS in busy areas, allowing location sensitive services, and managing QoS in residential areas.

To manage QoS in busy areas, Example Inc. uses the Core Network pre-defined PRA list CN1. Whenever any subscriber on the network enters an area included in CN1, the PCRF receives a notification and applies a policy that reduces QoS for that subscriber until the subscriber leaves the area included in CN1.

To allow location sensitive services, Example Inc. uses the UE-dedicated PRA list UE1 to manage a service that can only be used while roaming. UE1 establishes a home area for a subscriber or small group of subscribers. Whenever a subscriber whose home area is included in UE1 and who pays for the roaming service leaves the area included in UE1, the PCRF receives a notification and applies a policy that enables the roaming service.

Whenever the subscriber enters the area included in UE1, the PCRF receives a notification and applies a policy that disables the roaming service.

To manage QoS in residential areas, Example Inc. uses the UE-dedicated PRA list UE2 to establish a home area for a subscriber. Whenever the subscriber enters the home area UE2, the PCRF receives a notification to increase QoS for that subscriber until the subscriber leaves the home area UE2.

Creating a Core Network Pre-Configured Presence Reporting Area List

To create a Core Network pre-configured PRA list:

1. From the **Policy Server** section of the navigation pane, select **Presence Reporting Area Lists**.
The content tree displays the **Presence Reporting Area Lists** group.
2. From the content tree, select the **Presence Reporting Area Lists** group.
The Presence Reporting Area (PRA) List Administration page opens in the work area.
3. Click **Create PRA List**.
The New PRA List page opens.
4. Enter the following information:
 - a. **Name** — The unique name assigned to the PRA list.
The name can only contain the characters A–Z, a–z, 0–9, period (.), hyphen (-), and underline (_). The maximum length is 40 characters.
 - b. **Description/Location** (optional) — Free-form text.
 - c. **ID** — The unique identifying number of the PRA list. The ID must be a numeric value between 0 and 16777215.
 - d. **Type** — Select **Core Network pre-configured**.
5. Click **Save**.

The PRA list is created in the CMP database. You can now use it in a policy.

Creating a UE-dedicated Presence Reporting Area List

To create a UE-dedicated PRA list:

1. From the **Policy Server** section of the navigation pane, select **Presence Reporting Area Lists**.
The content tree displays the **Presence Reporting Area Lists** group.
2. From the content tree, select the **Presence Reporting Area Lists** group.
The Presence Reporting Area (PRA) List Administration page opens in the work area.
3. Click **Create PRA List**.
The New PRA List page opens.

4. Enter the following information:
 - a. **Name** — The unique name assigned to the PRA list.
The name can only contain the characters A–Z, a–z, 0–9, period (.), hyphen (-), and underline (_). The maximum length is 40 characters.
 - b. **Description/Location** (optional) — Free-form text.
 - c. **ID** — The unique identifying number of the PRA list. The ID must be a numeric value between 0 and 16777215.
 - d. **Type** — Select **UE-dedicated**.

The **Area List** page opens in the work area.
5. From the **Area List** page, click **Add**.
The Add Area window opens.
6. Select the type and enter the value.
For valid type-value combinations, see [Area List Type-Value Combinations](#).
The area is added to the Area List page.
7. Click **Save**.
The PRA list is created in the CMP database. You can now use it in a policy.

Area List Type-Value Combinations

TAI – Tracking Area Identity

MCC, MNC, TAC

RAI – Routing Area Identity

MCC, MNC, LAC, RAC

Macro eNodeB

MCC, MNC, MENB

Home eNodeB

MCC, MNC, HENB

ECGI – E-UTRAN Cell Global Identifier

MCC, MNC, ECI

SAI – Service Area Identity

MCC, MNC, LAC, SAC

CGI – Cell Global Identity

MCC, MNC, LAC, CI

MCC – Mobile Country Code

Three decimal digits

MNC – Mobile Network Code

Two or three decimal digits

TAC – Type Allocation Code

A decimal number between 0 and 65535

LAC – Location Area Code

A decimal number between 0 and 65535

RAC – Routing Area Code

A decimal number between 0 and 65535

MENB – Macro eNodeB

A decimal number between 0 and 268435455

HENB – Home eNodeB

A decimal number between 0 and 268435455

ECI

A decimal number between 0 and 268435455

SAC – Service Access Code

A decimal number between 0 and 65535

CI – Cell Identity

A decimal number between 0 and 65535

Modifying a Presence Reporting Area List

To modify a PRA list:

1. From the **Policy Server** section of the navigation pane, select **Presence Reporting Area Lists**.
The content tree displays the **Presence Reporting Area Lists** group.
2. From the content tree, select the **Presence Reporting Area Lists** group.
The Presence Reporting Area (PRA) List Administration page opens in the work area.
3. Select the PRA list you want to modify.
The PRA list information is displayed.
4. Click **Modify**.
The Modify PRA List page opens.
5. Modify PRA list information as required.
For information about the fields, see [Creating a Core Network Pre-Configured Presence Reporting Area List](#) and [Creating a UE-dedicated Presence Reporting Area List](#).
6. Click **Save**.
The PRA list is modified.

Deleting a Presence Reporting Area List

To delete a PRA list:



Note:

A PRA list cannot be deleted if it is being used in policy.

1. From the **Policy Server** section of the navigation pane, select **Presence Reporting Area Lists**.

The content tree displays the **Presence Reporting Area Lists** group.

2. From the content tree, select the **Presence Reporting Area Lists** group.

The Presence Reporting Area (PRA) List Administration page opens in the work area.

3. Delete the PRA list using one of the following methods:

- From the work area, click  (trash can icon), located to the right of the PRA list.
- From the content tree, select a PRA list and click **Delete**.

A confirmation message appears.

4. Click **OK**.

The PRA list is deleted.

Managing Quotas

This chapter describes how to create and manage Gx and Gy quotas in the CMP system.

In a wireless network, a quota sets a limit on a subscriber's usage, by any combination of volume (bytes of data), time (seconds of usage), or events (which are service specific). A quota can be applied by a policy rule trigger, or a quota can be applied by default if no policy rule is triggered. Quotas include pass, rollover, and top-up units.

**Note:**

The actual options you see depend on whether or not your CMP system is configured in wireless Gx mode, wireless Gy mode, or both.

About Quotas

A quota specifies restrictions on the amount of data volume, active session time, or service-specific events that a subscriber can consume. A single quota can express limits on any combination of volume, time, or events. Quotas can be associated with a time period during which activity is measured. Using the CMP server, you can define quota profiles. A quota profile specifies default values for quotas and defines how quotas are implemented. There are two types of quota profiles:

Plan

For more information about quota plans, see [About Quota Plans](#).

Pass

For more information about quota passes, see [About Quota Passes](#).

About Quota Plans

A quota plan describes a subscriber's basic, recurring service. Plans include policy characteristics such as time and volume limits. These characteristics can be computed automatically or through policy rules. Policy actions grant plans, based on a subscriber's tier or entitlement.

A basic quota refers to the quota associated with a plan and is used to handle recurring, periodic quotas typical of post-paid mobile data plans. The controls on a basic quota can be overridden by passes, rollovers, and top-ups.

Creating a Plan

In Gx mode, the MPE device can track and enforce a subscriber's total IP-CAN session time and volume usage by day, week, or month, or track aggregate volume usage and time per IP-CAN session. In Gy mode, the MPE device can track usage for multiple services based on time, volume, specific event, rollover information, and top-up information.

 Note:

If the optional 3GPP-MS-TimeZone AVP is enabled, the MPE device can reset the quota based on the user local time. If so, and user equipment enters a different time zone near the end of a quota cycle, the subscriber may find that the quota reset earlier than expected, or the service provider may find that the quota reset later than expected.

To create a plan:

1. From the **Policy Server** section of the navigation pane, select **Quota Profiles**.
The content tree displays the **Plans** and **Passes** groups.
2. Select the **Plans** group.
The Plan Administration page opens in the work area.
3. Click **Create Plan**.
The New Plan page opens.
4. Enter the following information:
 - a. **Name** — The name of the plan.
The name can only contain the characters A–Z, a–z, 0–9, period (.), hyphen (-), and underline (_). The maximum length is 255 characters.
 - b. **Description/Location** — Free-form text.
 - c. **Quota Profile Type** — Select whether the plan is assigned to an individual subscriber or a pool of subscribers. Select one of the following:
 - **Subscriber** (default)
 - **Pool**

 Note:

If you select **Pool**, items can be added to support the account (Max Leakage Threshold, Dynamic Grant, etc). After the plans are created, the plans are applied to subscribers.

- d. **Enable Dynamic Grant** (optional) — Specifies whether to track grant dynamically for the subscriber. This allows the granted values to be updated by the MPE device to the SPR. If the box is checked, then the configuration is set to true. The default value is false.
- e. **Max Leakage Threshold (MB)** — Maximum amount by which the usage can be exceeded. The default is 0 MB.
- f. **Max Sessions Used For Dynamic Grant** — Number of simultaneous sessions used in the dynamic grant algorithm for granting quota. Enabled when **Enable Dynamic Grant** is selected. The range is 1–2147483647 (Max 32-bit integer). The default is 10 sessions.

 Note:

Do not enter a value if dynamic grant is not enabled.

- g. **Minimum Grant Size**— The minimum plan amount granted by the MPE device. Enabled when **Enable Dynamic Grant** is selected. The value of the field depends upon the component (time/service-specific/volume) that is being granted by the MPE device:

- time — minimum number of seconds
- service-specific — minimum number of units
- volume (total/input/output) — minimum number of bytes

The default is 0.

 Note:

The value of the **Minimum Grant Size** field applies to all of the components that are granted by the MPE device. Make sure that the value reflects the minimum amount for all components. A low value could lead to a high number of messages being generated.

- h. **Reset Every** — Enter a value and select an interval from the list to specify how many times and how often the subscriber plan usage counters are reset. The default is 1 Month. Select one of the following intervals:

- **Months** (default) — The plan is reset when the specified number of months is met. To have yearly plans, specify a multiple of 12. For example, 36 months is a 3 year plan.
- **Weeks** — The **Choose Day** field appears. Weekly quotas are reset at midnight on the day you select from the list. The default day is Sunday.
- **Days** — The **Hour: Minute** field appears. Enter the hour and minute (in 24-hour format) at which quotas are reset. You must enter a time.
- **Never** — Go to step [m](#).

 Note:

You must specify a whole number greater than 0, a valid name in the **Billing Date Effective**, and enable the **DB.User.EnableBillingStartDate** expert setting to use this function. See the appropriate *CMP User's Guide* for more information about expert settings.

- i. **Reset Time Variable** — (Optional) Specify a variable to reset the time for the plan based on any substitutable policy variable in the subscriber profile.

The MPE device uses the variable name and substitutes it to calculate the actual reset time for the plan bucket. The substitutable variable names are the same as the substitutable policy variables, that is, variables that are substituted in policy actions, such as {User.State.Property1}. Curly braces ({}) can be used but are not required.

- For a monthly plan bucket, specify a variable whose value is either a billing day (between 1 and 31) or a time of day (such as 11:02), in which case the billing day is retrieved using the current mechanism (that is, use the subscriber profile; if not set, use the global billing day); or an actual date/time, following the `xsd:datetime` (similar to custom fields and entity states), specifying the first reset time for the quota bucket. The MPE device manages setting the `nextResetTime` on the quota usage records by computing the closest date/time in the future that is a multiple of a month away from the configured date/time, conserving the time of day.
 - For a weekly plan bucket, specify a variable containing either a time of day, in which case the day of the week is taken from the configured fixed day of the week, or a date/time representing the first reset time. The MPE device computes the next reset time similarly to the monthly bucket, but using multiple of one week instead.
 - For a daily plan bucket, specify a variable containing either a time of day or a date/time. In both cases, the MPE device computes the next reset time based on the time of day.
- j. **Report Offset Limit (minutes)** — The maximum minutes the MPE device add to the rest time for the quota when it calculates the session validation time. The range is 0 to 180.
- k. **Billing Date Effective Name** — Enter the Billing Date Effective name from a subscriber profile to use as the plan start date. This date is used as the start date of the plan and is used to calculate the next reset time. Enable the **DB.User.EnableBillingStartDate** expert setting to use this function. See the appropriate *CMP User's Guide* for more information about expert settings.
- l. **Collect Reset Statistics** — Enables the generation of reset statistics. If the reset frequency is set to **Never**, this field is hidden and the quota is never reset. The default is disabled.
- m. **Initial Total Volume Limit (bytes)** — Gx or Gy mode. Specifies the initial value for total volume units granted by the plan. Select one of the following:
- **None** (default). If you select **None**, then total volume units are not granted.
 - **Specify Variable** and enter a variable.
 - **Specify Limit** and enter a value.
- n. **Initial Upstream Volume Limit (bytes)** — Gx or Gy mode. Specifies the initial value for output volume units granted by the plan. Select one of the following:
- **None** (default). If you select **None**, then output volume units are not granted.
 - **Specify Variable** and enter a variable.
 - **Specify Limit** and enter a value.
- o. **Initial Downstream Volume Limit (bytes)** — Gx or Gy mode. Specifies the initial value for input volume units granted by the plan. Select one of the following:
- **None** (default). If you select **None**, then input volume units are not granted.
 - **Specify Variable** and enter a variable.

- **Specify Limit** and enter a value.
- p. **Volume Threshold Percentage (%)** — Gy mode only. Enter a threshold percentage.
Below this percentage of volume quota, the charging traffic function must re-authorize.
- q. **Initial Time Limit (seconds)** — Gx or Gy mode. Specifies the initial value for session time units granted by the plan. Select one of the following:
 - **None** (default). If you select **None**, then time units are not granted.
 - **Specify Variable** and enter a variable.
 - **Specify Limit** and enter a value.
- r. **Inactivity Detection Time (seconds)** — Specifies the interval after which the time measurement will stop for the monitoring key if no packets are received. Select one of the following:
 - **None** (default)
 - **Specify Limit** and enter a value in seconds.
- s. **Time Threshold Percentage (%)** — Gy mode only. Enter a threshold percentage.
Below this percentage of time quota, the charging traffic function must re-authorize.
- t. **Initial Service Specific Limit (events)** — Gy mode only. Specifies the initial value for service specific units granted by the plan. Select one of the following:
 - **None** (default). If you select **None**, then service specific units are not granted.
 - **Specify Variable** and enter a variable.
 - **Specify Limit** and enter a value.
- u. **Event Threshold Percentage (%)** — Gy mode only. Enter a threshold percentage.
When the event quota drops below this percentage, the charging traffic function must re-authorize. Select one of the following:
 - **None** (default)
 - **Specify Variable** and enter a variable.
 - **Specify Limit** and enter a value.
- v. **Interim Reporting Interval (seconds)** — Gy mode only. How often the charging traffic function (such as a GGSN) must report quota usage to the MPE device.
 - **None** (default)
 - **Specify Interval** and enter a value.
- 5. **Quota Exhaustion Action** — Gy mode only. The action the charging traffic function (such as a GGSN) takes when a subscriber reaches the quota grant:
 - **N/A** (default) — Take no action.
 - **TERMINATE** — Terminate the subscriber's session.
 - **REDIRECT** — If you select this action, additional configuration fields appear:
 - **Restriction Filters** — Enter a comma-separated list of Diameter IP Filter rules.
 - **Filter ID List** — Enter a comma-separated list of named filters on the charging traffic function.
 - **Redirect Server Type** — Select **IPv4**, **IPv6**, **URL**, or **SIP URI**.

- **Redirect Server Address** — Enter the server address
- **RESTRICT ACCESS** — If you select this action, additional configuration fields appear:
 - **Restriction Filters** — Enter a comma-separated list of Diameter IP Filter rules.
 - **Filter ID List** — Enter a comma-separated list of named filters on the charging traffic function.
- 6. **Quota Convention** — Select the name of a quota convention (see [About Quota Conventions](#)). This selection associates the plan with a rollover or top-up.

If you do not select a quota convention, then a default quota convention is assumed by the system. There is no rollover in a default quota convention.
- 7. Click **Save**.

The plan is defined in the CMP database and is displayed in the **Plans** group. The plan can now be used in a policy.

Modifying a Plan

To modify a plan:

1. From the **Policy Server** section of the navigation pane, select **Quota Profiles**.

The content tree opens, displaying the **Plans** and **Passes** groups.
2. From the content tree, select the **Plans** group.

The Plan Administration page opens, displaying the list of defined plans.
3. Select the plan you want to modify.

The work area displays information about the plan.
4. Click **Modify**.

The Modify Plan page opens.
5. Modify plan information as required.

For a description of the fields contained on this page, see [Creating a Plan](#).
6. Click **Save**.

The plan is modified.

Deleting a Plan

You cannot delete a plan that is referenced in a policy. Otherwise, to delete a plan:

1. From the **Policy Server** section of the navigation pane, select **Quota Profiles**.

The content tree opens, displaying the **Plans** and **Passes** groups.
2. From the content tree, select the **Plans** group.

The Plan Administration page opens, displaying the list of defined plans.
3. Delete the plan using one of the following methods:
 - From the work area, click  (trash can icon), located to the right of the plan.
 - From the content tree, select the plan and click **Delete**.

A confirmation message displays.

4. Click **OK** to delete the plan.

The plan is deleted.

Example: Creating and Using a Plan

An MPE device can grant time, data, or other service-specific units to subscribers. It can also limit grants based on quotas, either against plans or against limited exemptions such as passes, top-ups, and rollovers. The following is a simple wireless Gx example in which a monthly data usage quota is defined, and a policy is written for the MPE device to grant quota upon creation of a new session. The following values are defined and used:

- Plan name: MonthlyDataBasic
- Quota: 5 Gb (5,368,709,120 bytes) monthly
- Quota exhaustion action: Terminate

The policy rule is as follows:

```
where the request is creating a new session
grant total volume to 100 percent used for MonthlyDataBasic
accept message
```

This procedure consists of tasks described elsewhere. The steps must be performed in the order shown.

1. From the **Policy Server** section of the navigation pane, select **Quota Profiles**, select the **Plans** folder, and create the plan.

For more information, see [Creating a Plan](#).

The plan is defined in the CMP database.

2. From the **Policy Management** section of the navigation pane, select **Policy Library**, and define the policy.

For more information, see [Creating a Policy Rule](#).

The policy is defined in the CMP database.

3. From the **Policy Management** section of the navigation pane, select **Policy Library**, select the policy, and deploy it.

For more information, see the appropriate *CMP User's Guide*.

The policy is deployed to MPE devices in the Policy Management network.

About Quota Passes

A quota specifies restrictions on the amount of data volume, active session time, or service-specific events that a subscriber can consume. A single quota can express limits on any combination of volume, time, or events. Quotas can be associated with a time period during which activity is measured.

A pass is a one-time override that temporarily replaces or augments a subscriber's default plan or service.

For example, a subscriber who is normally not able to stream video to their device, but wants to view a special event, can purchase a pass that allows streaming.

Multiple passes can be assigned to the same subscriber. These passes are processed using the following criteria:

- The highest priority pass is processed first.
- If priorities are equal, the pass with the earliest expiration date/time is processed first.
- If expiration date/times are equal, the pass with the earliest purchase date/time is processed first.
- If purchase date/times are equal, the passes are processed in alphabetical order of the instance IDs.

The pass that is processed first according to these criteria is referred to as the "best" pass.

Passes can be added to pass groups. Adding a pass to a pass group associates that pass with all other passes in the pass group.

Pass groups can be used to determine pass expiration extension. The expiration date/time value of a new pass can be extended to match an expiration date/time value in the future of any pass in the same pass group.

A pass can belong to only one pass group. If the pass group is deleted, then the group field for each pass in the pass group is set to null. If the name of the pass group is changed, then the group field for each pass in the pass group is set to the new name.

Creating a Pass

To create a pass:

1. From the **Policy Server** section of the navigation pane, select **Quota Profiles**.
The content tree opens, displaying the **Passes** and **Plans** groups.
2. From the content tree, select the **Passes** group.
The content tree displays a list of passes and groups.
3. From the content tree, select the **ALL** group.
The Pass Administration page opens in the work area.
4. Click **Create Pass**.
The New Pass page opens.
5. Enter the following information:
 - a. **Name** — The name of the pass or top-up. The name can only contain the characters A–Z, a–z, 0–9, period (.), hyphen (-), and underline (_). The maximum length is 255 characters.
 - b. **Description/Location** — Free-form text.
 - c. **Enable Dynamic Grant** (optional) — Specifies whether to track grant dynamically for the subscriber. This will cause the granted values to be updated by the MPE device to the SPR. If the box is checked, then the configuration is set to true. The default value is false.
 - d. **Max Leakage Threshold (MB)** — Maximum amount by which the usage can be exceeded. The default is 0 MB.

- e. **Max Sessions Used For Dynamic Grant**— Number of simultaneous sessions used in the dynamic grant algorithm for granting quota. Enabled when **Enable Dynamic Grant** is selected. The range is 1–2147483647 (2GB–1). The default is 10 sessions.

 Note:

Do not enter a value if dynamic grant is not enabled.

- f. **Minimum Grant Size**— The minimum plan amount granted by the MPE device. Enabled when **Enable Dynamic Grant** is selected. The value of the field depends upon the component (time/service-specific/volume) that is being granted by the MPE device:

- time — minimum number of seconds
- service-specific — minimum number of units
- volume (total/input/output) — minimum number of bytes

The default is 0.

 Note:

The value of the **Minimum Grant Size** field applies to all of the components that are granted by the MPE device. Make sure that the value reflects the minimum amount for all components. A low value could lead to a high number of messages being generated.

- g. **Quota Profile Type** — Select whether the plan is assigned to an individual subscriber or a pool of subscribers. Select one of the following:

- **Subscriber** (default)
- **Pool**

 Note:

If you select **Pool**, items can be added to support the account (Max Leakage Threshold, Dynamic Grant, etc). After the plans are created, the plans are applied to subscribers.

- h. **Priority** — Defines the order of use when a subscriber has multiple instances of a pass. Higher priority passes are used before lower priority passes. A higher number indicates a higher priority.

The range is -32768–32767 (max 16-bit short).

- i. **Active Time Period** — The period during which the pass may be used.
- j. **Initial Total Volume Limit (bytes)** — Gx or Gy mode. Specifies the initial value for total volume units granted by the pass. Select one of the following:
- **None** (default). If you select **None**, then total volume units are not granted.
 - **Specify Limit** and enter a value.

- k. **Initial Upstream Volume Limit (bytes)** — Gx or Gy mode. Specifies the initial value for output volume units granted by the pass. Select one of the following:
 - **None** (default). If you select **None**, then output volume units are not granted.
 - **Specify Limit** and enter a value.
- l. **Initial Downstream Volume Limit (bytes)** — Gx or Gy mode. Specifies the initial value for input volume units granted by the pass. Select one of the following:
 - **None** (default). If you select **None**, then input volume units are not granted.
 - **Specify Limit** and enter a value.
- m. **Initial Time Limit (seconds)** — Gx or Gy mode. Specifies the initial value for session time units granted by the pass. Select one of the following:
 - **None** (default). If you select **None**, then time units are not granted.
 - **Specify Limit** and enter a value.
- n. **Inactivity Detection Time (seconds)** — Specifies the interval after which the time measurement will stop for the monitoring key if no packets are received. Select one of the following:
 - **None** (default)
 - **Specify Limit** and enter a value in seconds.
- o. **Initial Service Specific Limit (events)** — Gy mode only. Specifies the initial value for service specific units granted by the pass. Select one of the following:
 - **None** (default). If you select **None**, then service specific units are not granted.
 - **Specify Limit** and enter a value.
- p. **Interim Reporting Interval (seconds)** — Gy mode only. The number of seconds after which the gateway must revalidate any grant with the MPE. Select one of the following:
 - **None** (default)
 - **Specify Interval** and enter a value.
- q. **Duration** — The period after first use in which the pass must be used or expired.
- r. **Expiration Date Extension Method** — The criteria used for extending an expiration date.
Possible values are:
 - **NONE** — The expiration date/time value of this pass cannot be extended or used to extend the expiration date/time values of other passes.
 - **Name** — The expiration date/time value of this pass can be used to extend the date/time value of passes in the same pass group.
 - **Group** — The expiration date/time value of this pass can be extended to match the date/time value of any pass in the same pass group.

- s. **Quota Exhaustion Action** — Gy mode only. The action to take when all units in the pass are exhausted.

Possible values are:

- **N/A** (default) — Take no action.
- **TERMINATE** — Terminate the subscriber's session.
- **REDIRECT** — If you select this action, additional configuration fields appear:
 - **Restriction Filters** — Enter a comma-separated list of Diameter IP Filter rules.
 - **Filter ID List** — Enter a comma-separated list of named filters on the charging traffic function.
 - **Redirect Server Type** — Select **IPv4**, **IPv6**, **URL**, or **SIP URI**.
 - **Redirect Server Address** — Enter the server address
- **RESTRICT ACCESS** — If you select this action, additional configuration fields appear:
 - **Restriction Filters** — Enter a comma-separated list of Diameter IP Filter rules.
 - **Filter ID List** — Enter a comma-separated list of named filters on the charging traffic function.

6. Click **Save**.

The pass is defined in the CMP database and is displayed in the **Pass** group. The pass can now be used in a policy.

Modifying a Pass

To modify a pass:

1. From the **Policy Server** section of the navigation pane, select **Quota Profiles**.

The content tree opens, displaying the **Plans** and **Passes** groups.

2. From the content tree, select **Passes**.

The content tree displays a list of passes and pass groups. The initial group is **ALL**.

3. Select a pass.

The Pass Administration page opens in the work area.

Note:

If the pass has been added to a pass group, then the pass group name is shown in the **Group** field.

4. Click **Modify**.

The Modify Pass page opens.

5. Modify pass information.

For a description of the fields contained on this page, see [Creating a Pass](#).

 Note:

You cannot edit pass group information from this page. To assign the pass to a different pass group, you must remove the pass from the current pass group (see [Removing a Pass from a Pass Group](#)) and add the pass to a new pass group (see [Adding a Pass to a Pass Group](#)).

6. Click **Save**.

The pass is modified.

Deleting a Pass

To delete a pass:

1. From the **Policy Server** section of the navigation pane, select **Quota Profiles**.
The content tree opens, displaying the **Plans** and **Passes** groups.
2. From the content tree, select the **Passes** group.
The content tree displays a list of passes and pass groups. The initial group is **ALL**.
3. From the content tree, select the **ALL** group.
The Pass Administration page opens in the work area.
4. Delete the pass using one of the following methods:
 - From the work area, click  (trash can icon), located to the right of the pass.
 - From the content tree, select the pass and click **Delete**.A confirmation message displays.
5. Click **OK** to delete the pass.

The pass is deleted.

Creating a Pass Group

To create a pass group:

1. From the **Policy Server** section of the navigation pane, select **Quota Profiles**.
The content tree displays the **Plans** and **Passes** groups.
2. From the content tree, select the **Passes** group.
The content tree displays a list of passes and pass groups. The initial group is **ALL**.
3. Select the **ALL** group.
The Pass Administration page opens in the work area.
4. click **Create Group**.
The Create Group page opens in the work area.
5. Enter the following information:

- a. **Name** — The name of the pass group. The name can only contain the characters A–Z, a–z, 0–9, period (.), hyphen (-), and underline (_). The maximum length is 255 characters.
 - b. **Description/Location** — Free-form text.
 6. Click **Save**.
- The pass group is created.

Adding a Pass to a Pass Group

To add a pass to a pass group:

1. From the **Policy Server** section of the navigation pane, select **Quota Profiles**.
The content tree displays the **Plans** and **Passes** groups.
2. From the content tree, select the **Passes** group.
The content tree displays a list of passes and pass groups. The initial group is **ALL**.
3. From the content tree, select the pass group where you want to add the pass.
The Pass Administration page opens in the work area.
4. Click **Add Pass**.
The Add Pass page opens in the work area.
5. Select the pass that you want to add.

 Note:

Passes can belong to only one pass group.

6. Click **Save**.

A pass is added to the selected pass group. See [Removing a Pass from a Pass Group](#) for instructions on removing a pass from a pass group.

Modifying a Pass Group

To modify a pass group:

1. From the **Policy Server** section of the navigation pane, select **Quota Profiles**.
The content tree displays the **Plans** and **Passes** groups.
2. From the content tree, select the **Passes** group.
The content tree displays a list of passes and pass groups. The initial group is **ALL**.
3. From the content tree, select the pass group you want to modify.
The Pass Group Administration page opens in the work area.
4. Click **Modify**.
The Modify Group page opens in the work area.
5. Modify the pass group information.

 Note:

If you change the name of a pass group, then the **group** field for each pass in the pass group changes to the new name.

6. Click **Save**.

The pass group is modified.

Removing a Pass from a Pass Group

To remove a pass from a pass group:

1. From the **Policy Server** section of the navigation pane, select **Quota Profiles**.

The content tree displays the **Plans** and **Passes** groups.

2. From the content tree, select the **Passes** group.

The content tree displays a list of pass groups. The initial group is **ALL**.

3. From the content tree, select the pass group that contains the pass you want to remove.

The Pass Group Administration page opens in the work area.

4. Click  (scissors icon) located to the right of the pass.

The pass is removed from the pass group.

Deleting a Pass Group

 Note:

Deleting a pass group resets the group field of each pass in the pass group to null. The passes are not deleted from the system.

To delete a pass group:

1. From the **Policy Server** section of the navigation pane, select **Quota Profiles**.

The content tree displays the **Plans** and **Passes** groups.

2. From the content tree, select **Passes**.

The content tree displays a list of pass groups. The initial group is **ALL**.

3. From the content tree, select the pass group you want to delete.

The Pass Group Administration page opens in the work area.

4. Click **Delete**.

A confirmation message displays.

5. Click **OK** to delete the pass group.

The pass group is deleted.

Managing Quota Conventions

This chapter describes how to manage the usage of rollovers and top-ups using the CMP system.

In a wireless network, a quota convention controls top-ups and rollovers of plans.

**Note:**

The actual options you see depend on whether or not your CMP system is configured in wireless Gx mode, wireless Gy mode, or both.

About Quota Conventions

A quota convention controls top-ups and rollovers of plans.

**Caution:**

If a plan contains more than one type of counter (for example, time and volume), then ALL of the counters for that entire plan must be exhausted before a rollover and/or top-up for either type of counter is activated. Depending on how policy rules are written, this functionality could lead to an unintended effect on the end-user's service. If the intent is to apply separate limits on different units, then separate quotas should be defined and independent top-ups or rollovers may be applied.

Rollover

A rollover allows a subscriber to carry forward unused units from one billing cycle to another. For example, if a subscriber is allowed 10 gigabytes of data a month and only uses 9, the remaining gigabyte of data can be saved for use in the next month. Rollover units can accumulate and can be carried across multiple months. You can establish a quota convention that rollover units are consumed after plan units are exhausted, or before.

Top-up

A top-up allows a subscriber to obtain additional units for an existing plan. For example, if a plan allows 20 gigabytes of traffic per month, but near the end of the month the subscriber has only 1 gigabyte left, the subscriber can obtain an additional 5 gigabytes. These units are used after the initial units are exhausted and do not roll over.

Multiple top-ups can be present and enforced in the database at the same time and are processed by the MPE device. Multiple top-ups can be assigned to the same subscriber. These top-ups are consumed in the following order:

- The highest priority top-up is consumed first.
- If priorities are equal, the top-up with the earliest expiration date/time is consumed first.

- If expiration date/times are equal, the top-up with the earliest purchase date/time is consumed first.
- If purchase date/times are equal, the top-ups are consumed in alphabetical order of the instance IDs.

The top-up that is processed first according to these criteria is referred to as the best top-up.

You can establish a quota convention that top-up units are consumed after rollover units are exhausted, or before. However, plan units are always consumed before top-up units.

**Note:**

Top-ups are enabled using the **Quota Conventions** option. Top-up information is configured in an SPR database. See the Oracle Communications User Data Repository documentation for more information on the UDR product, and the Oracle Communications Enhanced Subscriber Profile Repository documentation for more information on the ESPR product.

Creating a Quota Convention

To create a quota convention:

1. From the **Policy Server** section of the navigation pane, select **Quota Conventions**.

The content tree displays the **Quota Conventions** group.

2. Select the **Quota Conventions** group.

The Quota Convention Administration page opens in the work area.

3. Click **Create Convention**.

The New Quota Convention page opens.

4. Enter the following information:

- a. **Name** — The name of the quota convention. The name can only contain the characters A–Z, a–z, 0–9, period (.), hyphen (-), and underline (_). The maximum length is 255 characters.

- b. **Description/Location** — Free-form text.

- c. **Rollover usage** — Specifies how rollover units are used with respect to top-up units.

The possible values are:

- **Default** — Rollover units are used before top-up units unless the highest priority top-up expires in the next 24 hours.
 - **Rollover after Top-up** — Top-up units are used before rollover units.
 - **Rollover before Top-up** — Rollover units are used before top-up units.
- d. **Interval percentage of the limits (%)** — The maximum percent of the units that can be rolled over during one billing cycle reset. The range is 0.0 – 100.0.

- e. **Max percentage of the limits (%)** — The maximum percent of the units that can be saved as a rolled limit at any time. The range is 0.0 – 1200.0.
5. Enable one or more of the following options:
- **Rollover Time Units** — Roll over time.
 - **Rollover Total Volume** — Roll over total volume.
 - **Rollover Input Volume** — Roll over input volume.
 - **Rollover Output Volume** — Roll over output volume.
 - **Rollover Service Specific Units** — Roll over service-specific units.
 - **Discard Rollover on Rollover Calculation** — Rollover units are not saved beyond one cycle.
 - **Consume Rollover before Quota** — Rollover units are used before plan units.

 Note:

Rollover units can be consumed before plan (quota) units, and top-up units can be consumed before rollover units. However, top-up units cannot be consumed before plan units.

- **Enable Top-ups** — Enable top-up units.
 - **Aggregate Quota** — Enables the quota usage calculation to be based on the quota plan, top-ups and rollovers. This option does not affect quota passes.
6. Click **Save**.

The quota convention is defined in the CMP database and can be used in a policy.

Modifying a Quota Convention

To modify a quota convention:

1. From the **Policy Server** section of the navigation pane, select **Quota Conventions**.
The content tree opens.
2. From the content tree, select the **Quota Conventions** group.
The Quota Convention Administration page opens, displaying the list of defined services.
3. Select the quota convention you want to modify.
The work area displays information about the quota convention.
4. Click **Modify**.
The Modify Quota Convention page opens.
5. Modify quota convention information as required.
For a description of the fields contained on this page, see [Creating a Quota Convention](#).
6. Click **Save**.

The quota convention is modified.

Associating a Quota Convention with a Plan

To associate a quota convention with a plan:

1. Create a quota convention. See [Creating a Quota Convention](#).
2. Create a plan or open an existing plan for modification. See [Creating a Plan](#) and [Modifying a Plan](#).
3. In the **Quota Convention** field, select the name of the quota convention you want to associate with the plan.
4. Click **Save** to save your changes.

The quota convention is associated with a plan.

Deleting a Quota Convention

To delete a quota convention:

1. From the **Policy Server** section of the navigation pane, select **Quota Conventions**.

The content tree displays the **Quota Conventions** group.

2. From the content tree, select the **Quota Conventions** group.

The Quota Convention Administration page opens, displaying the list of defined quota conventions.

3. Delete the quota convention using one of the following methods:

- From the work area, click  (trash can icon), located to the right of the quota convention.
- From the content tree, select the quota convention and click **Delete**.

A confirmation message displays.

4. Click **OK**.

The quota convention is deleted.

Managing RADIUS CoA Templates

This chapter describes how to create, modify, and delete RADIUS Change of Authorization (CoA) templates.

In a wireless network, the MPE device can function as a RADIUS server by receiving, acknowledging, and responding to RADIUS messages from clients, and generating CoA messages to RADIUS entities.

**Note:**

The actual options you see depend on whether or not your CMP system is configured in RADIUS mode.

About RADIUS CoA Templates

An MPE device can function as a RADIUS server in a wireless network. In this role it can perform the following actions:

- Receive a RADIUS message from a client system, acknowledge it, parse it, and then assemble and send a RADIUS Change of Authorization (CoA) message to some RADIUS client in the network to create, update, or delete services, which in this context are policies expressed using vendor-specific attributes (VSAs) or type-length-value structures (TLVs). Receipt of the message can trigger policy evaluation.
- Receive a subscriber update from an SPR system and then generate a CoA message to update or delete services. The identity of a subscriber is determined by parsing information in RADIUS messages using subscriber keys, which is then correlated with information obtained from the SPR system.
- Generate a CoA message to update or delete services because of the passage of time (keep-alive function).
- Evaluate and apply policies in response to RADIUS messages and supply CoA and other RADIUS messages. For example, the following CoA messages could potentially be processed:
 - 40: Disconnect-Request
 - 41: Disconnect-ACK
 - 42: Disconnect-NAK
 - 43: CoA-Request
 - 44: CoA-ACK
 - 45: CoA-NAK

Each vendor can use different or customized VSAs or TLVs. The CMP database includes a RADIUS dictionary that stores vendor, VSA, and TLV definitions. The dictionary includes standard IETF RADIUS TLVs. However, because RADIUS is an extensible protocol, new

vendors, VSAs, and TLVs can appear at any time. You can define custom vendors, VSAs, and TLVs and store them in the RADIUS dictionary. To support efficient assembly of CoA messages, you can define CoA templates that can include both known and custom values. The template can contain VSA and TLV values to be included in the CoA message, or left blank. If left blank, the corresponding values from the request or the session are used. If no value is found, the VSA or TLV is not included in the CoA message.

The CMP system displays RADIUS functions only if the appropriate mode is enabled. Contact My Oracle Support before attempting to change operating modes.

For information about creating custom vendor definitions, see [Managing Custom Vendors](#). For information about creating custom VSAs, see [Managing Custom VSAs](#). For information about subscriber keys, see [Managing Subscriber Keys](#).

**Note:**

The actual options you see depend on whether or not your CMP system is configured in RADIUS mode.

Creating a RADIUS CoA Template

To create a RADIUS CoA template:

**Note:**

The actual options you see depend on whether or not your CMP system is configured in RADIUS mode.

1. From the **Policy Server** section of the navigation pane, select **RADIUS CoA Template**.

The content tree displays the **RADIUS CoA Template** group.

2. Select the **RADIUS CoA Template** group.

The RADIUS CoA Template Administration page opens in the work area.

3. Click **Create RADIUS CoA Template**.

The New RADIUS CoA Template page opens. You can now define a template by name and assign attributes to include in it.

4. Enter the **Name** you assign to the template.

5. To add an attribute:

- a. Click **Add**.

The Add Response window opens.

- b. Select the available **Vendor** from the list:

- **IETF** (default)
- **3GPP**

- **3GPP2**
- **Camiant**
- **Cisco**
- **Cisco-BBSM**
- **Cisco-VPN3000**
- **Cisco-VPN5000**
- **Juniper**
- **Juniper-M-Series**
- [defined custom vendors]

**Note:**

Any defined custom vendors are displayed at the end of the list. For information, see [Managing Custom Vendors](#)

- c. Select **TLV/VSA** from the list.
- The choices are extensive and are not listed here.

**Note:**

Any defined custom TLVs or VSAs are displayed at the end of the list. For information see [Managing Custom VSAs](#).

- d. **Default Value** — Enter the default value for the TLV or VSA.
6. (Optional) To add, modify, or delete attributes:
- Cloning an entry in the table
 - a. Select an entry in the table.
 - b. Click  **Clone**. The Clone window opens with the information for the entry.
 - c. Make changes as required.
 - d. Click **Save**. The entry is added to the table.
 - Editing an entry in the table
 - a. Select the entry in the table.
 - b. Click  **Edit**. The Edit Response window opens, displaying the information for the entry.
 - c. Make changes as required.
 - d. Click **Save**. The entry is updated in the table.
 - Deleting a value from the table
 - a. Select the entry in the table.
 - b. Click  **Delete**. A confirmation message displays.
 - c. Click **Delete** to remove the entry. The entry is removed from the table.

7. Click **Save**.

The RADIUS CoA template is created.

Modifying a RADIUS CoA Template

To modify a RADIUS CoA template:

1. From the **Policy Server** section of the navigation pane, select **RADIUS CoA Template**.

The RADIUS CoA Template Administration page opens in the work area and lists the defined RADIUS CoA templates.

2. Select the template you want to modify.

The RADIUS CoA Template Administration page displays information about the template.

3. Click **Modify**.

The Modify RADIUS CoA Template page opens.

4. Modify the template information as required.

For a description of the fields contained on this page, see [Creating a RADIUS CoA Template](#).

5. Click **Save**.

The RADIUS CoA template is modified and the changes are deployed to MPE devices.

Deleting a RADIUS CoA Template

To delete a RADIUS CoA template:

1. From the **Policy Server** section of the navigation pane, select **RADIUS CoA Template**.

The RADIUS CoA Template Administration page opens in the work area, listing the defined RADIUS CoA templates.

2. Delete the RADIUS CoA template using one of the following methods:

- From the work area, click  (trash can icon) located to the right of the RADIUS CoA template.
- From the content tree, select the RADIUS CoA template and click **Delete**.

A confirmation message displays.

3. Click **OK**.

The RADIUS CoA template is deleted.

Example of Creating and Using a RADIUS CoA Template

In response to a RADIUS message such as `Accounting-Start`, an MPE device can use a RADIUS CoA template to send a policy, expressed using VSAs and TLVs, to a BNG device for a specific subscriber. The following is a simple example in which a RADIUS CoA template containing one VSA from a new vendor is defined, and a policy

is written for the MPE device to send the RADIUS CoA to a BNG device upon receipt of a `RADIUS Accounting-Start` message. The following values are defined and used:

- Vendor name and ID: EquipTel (3561)
- VSA name: DSLF-Maximum-Interleaving-Delay-Downstream
- VSA code: 141
- VSA type: single-value integer
- CoA Template name: RADIUS CoA Template EquipTel

The policy rule is as follows:

```
where the RADIUS accounting request is RADIUS Accounting-Start
send CoA with RADIUS CoA Template EquipTel
accept message
```

This procedure consists of tasks described elsewhere. The steps must be performed in the order shown.



Note:

The actual options you see depend on whether or not your CMP system is configured in RADIUS mode.

1. From the **Policy Server** section of the navigation pane, select **Custom Vendors**, and define the custom vendor.
For more information, see [Creating a Custom Vendor](#).
The custom vendor is defined in the RADIUS dictionary.
2. From the **Policy Server** section of the navigation pane, select **Custom VSA Definitions**, and define the custom vendor.
For more information, see [Creating a Custom VSA](#).
The custom VSA is defined in the RADIUS dictionary.
3. From the **Policy Server** section of the navigation pane, select **RADIUS CoA Template**, and define the RADIUS CoA template.
For more information, see [Creating a RADIUS CoA Template](#).
The RADIUS CoA template is defined in the CMP database.
4. From the **Policy Management** section of the navigation pane, select **Policy Library**, and define the policy.
For more information, see [Creating a Policy Rule](#).
The policy is defined in the CMP database.
5. From the **Policy Management** section of the navigation pane, select **Policy Library**, select the policy, and deploy it.
For more information, see the *CMP Wireless User's Guide*.
The policy is deployed to MPE devices in the Policy Management network.

The RADIUS CoA template is used as follows:

1. After the BNG device successfully authenticates a subscriber, it sends a RADIUS Accounting-Start message to the MPE device.
2. The MPE device fetches the subscriber's profile from an SPR database.
3. The MPE device subscribes to the SPR database for changes to the profile of the subscriber.
4. Based on the subscriber's profile and other conditions, the MPE device determines which policy and charging control (PCC) rule to install, and sends a RADIUS CoA request to install a service on the BNG device. The message includes the custom VSA from the custom vendor, as specified by the RADIUS CoA template.
5. The BNG device installs the service and sends an acknowledgment message to the MPE device.
6. The BNG device periodically sends Interim-Update messages, which the MPE device interprets as keep-alive messages indicating that the BNG device is still operational.

Managing Retry Profiles

This chapter describes how to create and manage retry profiles in the CMP system.

In a wireless network, a retry profile specifies the circumstances under which installation of a policy and charging control (PCC) rule is retried if the rule is reported to have failed.

About Retry Profiles

A retry profile specifies the circumstances under which installation of a Policy and Charging Control (PCC) or an application detection control (ADC) rule is retried if the rule is reported to have failed (for example, because the establishment of a network-initiated bearer failed), as indicated by a Charging-Rule-Report or an ADC-Rule-Report. The retry action consists of repeatedly trying up to a maximum number of retry cycles consisting of several configurable parameters and an exponential back off algorithm to calculate the wait time between successive retry attempts. Generally, each retry cycle would consist of a small number of retry attempts and a relatively large **Back Off Interval** between each retry cycle.

For example, a Charging-Rule-Report reports a failure to establish a dedicated bearer. Using the configured Retry Profile, an attempt is made to establish a dedicated bearer after the **Initial Retry Interval**. Should the attempt fail, another retry attempt is made within the **Maximum Retry Interval** period. Attempts are repeated until the number of attempts reaches the **Maximum Retry Attempts**. This concludes a retry cycle. The next retry cycle begins after the configured time-period **Back Off Interval**.



Note:

A retry profile can be applied by a policy rule trigger.



Note:

You can define multiple retry profiles, each with different parameter values.

Creating a Retry Profile

To create a retry profile:

1. From the **Policy Server** section of the navigation pane, select **Retry Profile**.
The content tree displays the **Retry Profile** group.
2. Select the **Retry Profile** group.
The Retry Profile Administration page opens in the work area and lists any available retry profiles.
3. Click **Create Retry Profile**.

The New Retry Profile page opens.

4. Enter the **Name** for the profile.

The name can only contain the characters A–Z, a–z, 0–9, period (.), hyphen (-), and underline (_). The maximum length is 255 characters.

5. Enter the **Description/Location**.

Free-form text describing the profile.

6. Select the **Retry Profile Type** from the list:

The available choices are:

- For Wireless:
PCC Retry Profile and **ADC Retry Profile** (default).
- For Cable and Wireline:
Best Effort — Transmission opportunities are granted on a first-come, first-served basis. Appropriate for upstream service flows such as Web browsing, email, or instant messaging.

7. Enter the **Maximum Retry Attempt (per Retry Cycle)**.

The maximum number of retry attempts during a retry cycle in the range from 1 to 10. The default is 5.

8. Enter the **Initial Retry Interval**.

The length of time to wait, in seconds, after a reported failure or the end of the Back Off Interval before retrying. Enter a value from 0 to 30 seconds. The default is 10 seconds.

 Note:

To specify a retry immediately after a reported failure, enter 0.

9. Enter the **Maximum Retry Interval**.

The maximum wait, in seconds, after a reported failure or the end of the Back Off Interval before retrying during a retry cycle. Enter a value from 1 to 180 seconds. The default is 60 seconds.

10. Enter the **Back Off Interval**.

The interval from 1 to 86400 seconds between successive retry cycles. The default is 300 seconds.

11. Enter the **Maximum Retry Cycles**.

The number of retry cycles ranging from 1 to 4. The default value is 1 cycle.

12. **Rule Failure Code**

The upper box lists available rule failure codes. The lower box lists rule failure codes installed in the profile.

 Note:

The failure codes `RESOURCES_LIMITATION` and `RESOURCE_ALLOCATION_FAILURE` are installed by default.

- To add a rule failure code to the profile, select it in the upper box and click **Add**.
- To remove a rule failure code from the profile, select it in the lower box and click **Delete**.

 Note:

If the total number of retry attempts (**Maximum Retry Attempt** multiplied by the **Maximum Retry Cycles**) exceeds 12, the CMP displays a warning message that the configuration might increase the signaling load in the network and asks if you want to continue with the specified settings.

 Note:

If the profile does not contain any rule failure codes, the MPE device retries the rule installation regardless of the failure code reported.

13. Click **Save**.

The retry profile is defined in the CMP database and can now be used in a policy.

Modifying a Retry Profile

To modify a retry profile:

1. From the **Policy Server** section of the navigation pane, select **Retry Profile**.
The content tree opens.
2. From the content tree, select the **Retry Profile** group.
The Retry Profile Administration page opens, displaying the list of defined retry profiles.
3. Select the profile you want to modify.
The profile information is displayed.
4. Click **Modify**.
The Modify Retry Profile page opens.
5. Modify profile information.
For a description of the fields contained on this page, see [Creating a Retry Profile](#).
6. Click **Save**.
The retry profile is modified.

Deleting a Retry Profile

To delete a retry profile:

1. From the **Policy Server** section of the navigation pane, select **Retry Profile**.
The content tree opens.
2. From the content tree, select the **Retry Profile** group.
The Retry Profile Administration page opens, displaying the list of defined retry profiles.
3. Delete the retry profile using one of the following methods:
 - From the work area, click  (trash can icon), located to the right of the retry profile.
 - From the content tree, select the retry profile and click **Delete**.A confirmation message displays.
4. Click **OK** to delete the retry profile.

The retry profile is deleted.



Note:

If the retry profile is used in a policy action, the deletion fails.

Managing Roaming Profiles

This chapter describes how to create and manage roaming profiles in the CMP system.

A roaming profile allows a set of roaming attributes to be defined and then applied to specific subscribers.

About Roaming Profiles

Roaming Profiles are used in conjunction with the S9 interface. The S9 interface allows the PCRF to support LTE roaming services such as Voice over LTE. This is done by establishing S9 and Rx sessions between the Home PCRF (H-PCRF) and the Visiting PCRF (V-PCRF).

Roaming Profiles are used to allow or disallow S9 requests at the H-PCRF, and to validate messages coming from the H-PCRF and going to the V-PCRF. A V-PCRF also uses the roaming profile to decide whether to report UE Time zone and location information to the H-PCRF. You can define up to 50 profiles, each with different parameters.

S9 interface functionality must be turned on before roaming profiles can be used. By default, the PCRF cannot initiate or accept S9 requests. To turn initiate or accept on, modify the S9 settings using the **Policy Server** tab in the Policy Server configuration. If an MRA is deployed in the network, the primary and secondary DEA (or S9 peer) can be configured using the **MRA** tab located in the MRA configuration.



Note:

At least one MRA Diameter Routing Peer must be defined to configure the primary/secondary DEA.

Creating a Roaming Profile

To create a roaming profile:

1. From the **Policy Server** section of the navigation pane, select **Roaming Profile**.
The content tree displays the **Roaming Profile** group.
2. Select **Roaming Profile** group.
The Roaming Profile Administration page opens in the work area, listing available roaming profiles.
3. Click **Create Roaming Profile**.
The New Roaming Profile page opens.
4. On the **Configuration** tab, enter the following information:
 - a. **Name** — Unique name assigned to the roaming profile. The name can only contain the characters A–Z, a–z, 0–9, period (.), hyphen (-), and underline (_). The maximum length is 255 characters.

- b. Description** — Free-form text describing the profile. A maximum of 255 characters can be entered.
 - c. S9 Support** — Select the type of S9 interface support allowed for this roaming profile. The available choices are:
 - **None** (default)—S9 support is not allowed.
 - **Both**—S9 support is allowed for subscribers with MCC-MNC for both visiting and home functionalities.
 - **Visiting**—S9 support is allowed for visiting subscribers with MCC-MNC VPCRF functionality.
 - **Home**—S9 support is allowed for home subscribers with MCC-MNC HPCRF functionality.If **Both** or **Visiting** is selected, the **QoS Validation Parameters** tab becomes available.
 - d. Report over S9** — Select the content to be reported using the S9 interface. The available content is **User Location** and **Timezone**. Both choices are unchecked (not reported) by default. This option is enabled only when S9 support is either **Visiting** or **Both**.
- 5. If the QoS Validation Parameters tab is available, enter the following information:**
 - a. Uplink Aggregated Guaranteed Bitrate (bps)** — Enter the maximum uplink guaranteed bitrate to be allowed for a PDN connection across all GBR (Guaranteed Bit Rate) bearers.

Integer value in the inclusive range of 0 to 9,223,372,036,854,775,807 (without commas), that is, 0 to $2^{63}-1$. If this field is left blank, no validation is performed.
 - b. Downlink Aggregated Guaranteed Bitrate (bps)** — Enter the maximum downlink guaranteed bitrate to be allowed for a PDN connection across all GBR (Guaranteed Bit Rate) bearers.

Integer value in the inclusive range of 0 to 9,223,372,036,854,775,807 (without commas), that is, 0 to $2^{63}-1$. If this field is left blank, no validation is performed.
 - c. Uplink Aggregated Maximum Bitrate (bps) for Guaranteed Bitrate Bearers** — Enter the maximum uplink bitrate to be allowed for a PDN connection across all GBR (Guaranteed Bit Rate) bearers.

Integer value in the inclusive range of 0 to 9,223,372,036,854,775,807 (without commas), that is, 0 to $2^{63}-1$. If this field is left blank, no validation is performed.
 - d. Downlink Aggregated Maximum Bitrate (bps) for Guaranteed Bitrate Bearers** — Enter the maximum downlink bitrate to be allowed for a PDN connection across all GBR (Guaranteed Bit Rate) bearers.

Integer value in the inclusive range of 0 to 9,223,372,036,854,775,807 (without commas), that is, 0 to $2^{63}-1$. If this field is left blank, no validation is performed.
 - e. Uplink APN Aggregate Maximum Bitrate (bps)** — Specify the maximum aggregate bitrate associated with a specific access point (APN) for the uplink direction.

Integer value in the inclusive range of 0 to 9,223,372,036,854,775,807 (without commas), that is, 0 to $2^{63}-1$. If this field is left blank, no validation is performed.

- f. **Downlink APN Aggregate Maximum Bitrate (bps)** — Specify the maximum aggregate bitrate associated with a specific access point (APN) for the downlink direction.

Integer value in the inclusive range of 0 to 9,223,372,036,854,775,807 (without commas), that is, 0 to $2^{63}-1$. If this field is left blank, no validation is performed.

- g. **Acceptable Default EPS Bearer QoS** Under this heading are the following variables:

- **QoS Class Identifiers** — Check mark one or more QoS class identifiers (QCI) to be associated with this roaming profile or enter a value between 1 and 254 in the **Others** field and click **Add**. This identifies the set of Default EPS Bearer QCI values that are acceptable at the VPCRF. When one or more values is selected, the VPCRF function validates the QCI value from the Default-EPS-Bearer-QoS AVP, sent by the HPCRF against the configured set of values in the roaming profile. If no identifier is check marked, the default is 9. The options are:
 - **1 (Conversation Speech)**
 - **2 (Conversational)**
 - **3 (Streaming Speech)**
 - **4 (Streaming)**
 - **5 (Interactive with priority 1 signaling)**
 - **6 (Interactive with priority 1)**
 - **7 (Interactive with priority 2)**
 - **8 (Interactive with priority 3)**
 - **9 (Background)** (default)
 - **65 (MC-PTT)**
 - **66 (PTT Voice)**
 - **69 (MC-PTT Signaling)**
 - **70 (MC Data)**

 Note:

QCI values between 1 and 254 are supported. Values other than 1-9, 65, 66, 69, and 70 are undefined.

- **ARP Priority Level (Comma Separated Values)** — This field identifies the set of Default EPS Bearer ARP Priority values that are acceptable at the VPCRF. The VPCRF function validates the ARP Priority value from the Default-EPS-Bearer-QoS AVP, sent by the HPCRF against the configured set of values in the roaming profile. When limited resources are encountered, the Allocation and Retention Priority (ARP) priority level tells the system to either accept or reject an establishment or modification of bearer request.
Enter one or more priority values separated by a comma. Note that the VPCRF checks to see if the incoming message from the HPCRF contains the Default-EPS-Bearer-Qos AVP. If it does, the ARP Priority Level in that AVP is added to

the list of selected values allowed by the roaming profile. Valid priority level values are 1 through 9. Default value is none (or empty).

- **ARP Preemption Capability** — This field configures whether preemption capability is enabled or disabled in the PCC action profile. Preemption aids in call admission control and lets the gateway accommodate higher priority bearers over lower priority bearers (for example, when resources are unusually limited or for emergency services), based on the ARP Priority Level and ARP Preemption Vulnerability. Options from the pulldown menu are **BOTH**, **PREEMPTION_CAPABILITY_ENABLED**, and **PREEMPTION_CAPABILITY_DISABLED**. The default value is **BOTH**. Note that the VPCRF checks to see if the incoming message from the HPCRF contains the Default-EPS-Bearer-Qos AVP. If it does, the ARP Preemption Capability in that AVP overrides any value selected here.
- **ARP Preemption Vulnerability** — This field identifies the Default EPS Bearer ARP Preemption Vulnerability values that are acceptable at the VPCRF. The VPCRF function validates the ARP Preemption Vulnerability value from the Default-EPS-Bearer-QOS AVP, sent by the HPCRF against the configured value in the roaming profile. Options from the pulldown menu are **Both**, **Preemption_vulnerability_enabled**, and **Preemption_vulnerability_disabled**. Default value is **Both**. Note that the VPCRF checks to see if the incoming message from the HPCRF contains the Default-EPS-Bearer-Qos AVP. If it does, the ARP Preemption Vulnerability in that AVP overrides any value selected here.

6. On the **Associated MCC-MNC Lists** tab, highlight the match lists in the **Available** column and click the right arrow (>>) button to move them to the **Associated** column.

See [Managing Match Lists](#) for information on creating a match list.

7. Click **Save**.

The roaming profile is defined in the CMP database and can now be used in a policy.

Modifying a Roaming Profile

To modify a roaming profile:

1. From the **Policy Server** section of the navigation pane, select **Roaming Profile**.
The content tree opens.
2. From the content tree, select the **Roaming Profile** group.
The Roaming Profile Administration page opens, displaying the list of defined roaming profiles.
3. Select the profile you want to modify.
Profile information is displayed.
4. Click **Modify**.
The Modify Roaming Profile page opens.
5. Modify profile information as required.
For a description of the fields contained on this page, see [Creating a Roaming Profile](#).
6. When you finish, click **Save** (or **Cancel** to abandon your changes).

The roaming profile is modified.

Deleting a Roaming Profile



Note:

A roaming profile cannot be deleted if any policy is referencing it.
To delete a roaming profile:

1. From the **Policy Server** section of the navigation pane, select **Roaming Profile**.
The content tree opens.
2. From the content tree, select the **Roaming Profile** group.
The Roaming Profile Administration page opens, displaying the list of defined roaming profiles.
3. Delete the roaming profile using one of the following methods:
 - From the work area, click  (trash can icon) located to the right of the roaming profile.
 - From the content tree, select the roaming profile and click **Delete**.
A confirmation message displays.
4. Click **OK**.
The roaming profile is deleted.

Managing Service Classes

This chapter defines how to create and manage service classes in the CMP system.

In a cable network, a service class corresponds to a DOCSIS traffic description defined in a cable modem termination system (CMTS).

**Note:**

Service Classes is a function that is applicable to Cable mode only.

About Service Classes

A service class corresponds to a DOCSIS traffic description defined in a cable modem termination system (CMTS). You can define service classes using the CMP system, load them using the OSSI/XML interface, or discover them using the SNMP interface.

**Note:**

Service Classes is a function that is applicable to Cable mode only.

Creating a Service Class

**Note:**

Service Classes is a function that is applicable to Cable mode only.

To create a service class:

1. From the **Policy Server** section of the navigation pane, select **Service Classes**.
The content tree displays the **Service Classes** group.
2. Select the **Service Classes** group.
The Service Class Administration page opens in the work area, listing available service classes.
3. Click **Create Service Class**.
The New Service Class page opens.
4. Enter the following information:
 - a. **Name** — The name assigned to the service class.

b. Scheduling Type — Select from the following:

- **Downstream** (default) — Defined through a similar set of QoS parameters that are associated with the best-effort scheduling type on upstream service flows. Appropriate for all downstream service flows.
- **Best Effort** — Transmission opportunities are granted on a first-come, first-served basis. Appropriate for upstream service flows such as Web browsing, e-mail, or instant messaging.
- **Non Real Time Polling** — Cable modems are polled at a fixed interval for queued data. Appropriate for upstream service flows that require high throughput, and traffic that requires variable-sized data grants on a regular basis, such as high-bandwidth FTP.
- **Real Time Polling** — Cable modems are polled at a fixed but short interval for queued data. Appropriate for upstream service flows of real-time traffic that generate variable-sized data packets on a periodic basis and have inflexible latency and throughput requirements, such as MPEG video.
- **Unsolicited Grant Service** — A fixed-size grant is offered to service flows at fixed intervals without additional polling or interaction. Appropriate for upstream service flows of real-time traffic that generate fixed-size data packets on a periodic basis, such as VoIP.
- **Unsolicited Grant Service with Activity Detect** — When there is activity, the CMTS sends unsolicited fixed grants at fixed intervals to the cable modem. When there is no activity, the CMTS sends unicast poll requests to the cable modem to conserve unused bandwidth. Appropriate for upstream service flows that include silence suppression.

c. Maximum Traffic Rate (bps) — The maximum sustained rate, in bits per second, at which traffic can operate over the service flow.

Enter an integer between 0 and 4294967295.

This field applies to the **Downstream**, **Best Effort**, **Non Real Time Polling**, and **Real Time Polling** scheduling types.

d. Minimum Reserved Rate (bps) — The guaranteed minimum rate, in bits per second, that is reserved for the service flow.

Enter an integer between 0 and 4294967295.

This field applies to the **Downstream**, **Best Effort**, **Non Real Time Polling**, and **Real Time Polling** scheduling types.

e. Unsolicited Grant Size (bytes) — The size, in bytes, of the individual data grants provided to the service flow.

Enter an integer between 0 and 65535.

This field applies to the **Unsolicited Grant Service** and **Unsolicited Grant Service with Activity Detect** scheduling types.

f. Nominal Grant Interval (usecs) — The nominal interval, in microseconds, between successive unsolicited data grant opportunities for this service flow.

Enter an integer between 0 and 4294967295.

This field applies to the **Unsolicited Grant Service** and **Unsolicited Grant Service with Activity Detect** scheduling types.

- g. Grants per Interval** — The actual number of data grants given to the service flow during each nominal grant interval.

Enter an integer between 0 and 127.

This field applies to the **Unsolicited Grant Service** and **Unsolicited Grant Service with Activity Detect** scheduling types.

5. Click **Save**.

The service class is defined in the CMP database and can now be used in a policy.

Modifying a Service Class

To modify a service class:

1. From the **Policy Server** section of the navigation pane, select **Service Classes**.

The content tree opens.

2. From the content tree, select the **Service Classes** group.

The Service Class Administration page opens, displaying the list of defined service classes.

3. Select the service class.

Service class information is displayed.

4. Click **Modify**.

The Modify Service Class page opens.

5. Modify service class information.

For a description of the fields contained on this page, see [Creating a Service Class](#).

6. Click **Save**.

The service class is modified.

Deleting a Service Class

To delete a service class:

1. From the **Policy Server** section of the navigation pane, select **Service Classes**.

The content tree opens.

2. From the content tree, select the **Service Classes** group.

The Service Class Administration page opens displaying the list of defined service classes.

3. Delete the service class using one of the following methods:

- From the work area, click  (trash can icon), located to the right of the service class.
- From the content tree, select the service class and click **Delete**.

A confirmation message displays.

4. Click **OK** to delete the service class.

The service class is deleted.

Managing Services and Rating Groups

This chapter describes how to create and manage Gy services and rating groups in the CMP system.

About Services

In a wireless network, a service is an identification of a class of traffic:

- Voice
- Peer-to-peer
- Multimedia

You can apply a quota or a rating group (but not both) to a service.

For organizational purposes, you can associate services into rating groups. This is a convenient way of allowing multiple services to share the same quota.



Note:

The actual options you see depend on whether or not your CMP system is configured in wireless Gx mode, wireless Gy mode, or both. For information on defining quotas, see [Managing Quotas](#).

Creating a Service



Note:

Services is a function that is applicable to Gy interfacing mode only.

To create a service:

1. From the **Policy Server** section of the navigation pane, select **Services & Rating Groups**.

The content tree displays the **Services & Rating Groups** group.

2. Select the **Services & Rating Groups** group.

The Service Administration page opens in the work area.

3. Click **Create Service**.

The New Service page opens.

4. Enter the following information:

- a. **Name** (required) — The name assigned to the service. The name can only contain the characters A–Z, a–z, 0–9, period (.), hyphen (-), and underline (_). The maximum length is 255 characters.
 - b. **Description/Location** — Free-form text.
 - c. **Service Identifier** — A unique numeric identifier.
 - d. **Rating Group** — Select **None** (default) or one of the rating groups defined in the CMP database.
 - e. **Quota** — Select **None** (default) or one of the quotas defined in the CMP database.
5. Click **Save**.
- The service is created.

Modifying a Service

To modify a service:

1. From the **Policy Server** section of the navigation pane, select **Services & Rating Groups**.
The content tree opens.
2. From the content tree, select the **Services** group.
The Service Administration page opens, displaying the list of defined services.
3. Select the service you want to modify.
The work area displays information about the service.
4. Click **Modify**.
The Modify Service page opens.
5. Modify service information as required.
For a description of the fields contained on this page, see [Creating a Service](#).
6. Click **Save**.
The service is modified.

Deleting a Service

To delete a service:

1. From the **Policy Server** section of the navigation pane, select **Services & Rating Groups**.
The content tree opens.
2. From the content tree, select the **Services** group.
The Service Administration page opens, displaying the list of defined services.
3. Delete the service using one of the following methods:
 - From the work area, click  (trash can icon), located to the right of the service.
 - From the content tree, select the service and click **Delete**.

A conformation message displays.

4. Click **OK** to delete the service.

The service is deleted.

About Rating Groups

For organizational purposes, you can combine services into rating groups. Quotas apply to all the services in a rating group. After a rating group is created, you can populate it with services.



Note:

Rating groups are applicable in the Gy interfacing mode only.

Creating a Rating Group



Note:

Rating groups is a function that is applicable to Gy interfacing mode only.

To create a rating group:

1. From the **Policy Server** section of the navigation pane, select **Services & Rating Groups**.
The content tree displays the **Services & Rating Groups** group.
2. Select the **Services & Rating Groups** group.
The Service Administration page opens in the work area.
3. Click **Create Rating Group**.
The Create Rating Group page opens.
4. Enter the following information:
 - a. **Name** (required) — The name assigned to the rating group. The name can only contain the characters A–Z, a–z, 0–9, period (.), hyphen (-), and underline (_). The maximum length is 255 characters.
 - b. **Description/Location** — Free-form text.
 - c. **Rating Group Identifier** — A unique numeric identifier.
 - d. **Quota** — Select **None** (default) or one of the quotas defined in the CMP.
5. Click **Save**.

The rating group is created and stored in the **Services & Rating Groups** folder.

Adding a Service to a Rating Group

To add a service to a rating group:

1. From the **Policy Server** section of the navigation pane, select **Services & Rating Groups**.

The content tree displays the **Services & Rating Groups** group.

2. In the content tree, select the rating group to which you want to add a service.

The Rating Group Administration page opens in the work area.

3. Click **Add Service**.

The Add Service page opens, displaying the services not already part of the group.

4. Select the service you want to add; use the Ctrl or Shift keys to select multiple services.

5. Click **Save**.

The service is added to the selected rating group.

Modifying a Rating Group

You cannot rename a rating group that is referenced in a policy. Otherwise, to modify a rating group:

1. From the **Policy Server** section of the navigation pane, select **Services & Rating Groups**.

The content tree displays the **Services & Rating Groups** group.

2. In the content tree, select the rating group you want to modify.

The Rating Group Administration page opens displaying the information about the rating group.

3. Click **Modify**.

The Modify Rating Group page opens.

4. Make changes. For information about the fields on this page, see [Creating a Rating Group](#).

5. Click **Save**.

The rating group is modified.

Removing a Service from a Rating Group

Removing a service from a rating group does not delete the service. To delete a service, see [Deleting a Service](#).

To remove a service from a rating group:

1. From the **Policy Server** section of the navigation pane, select **Services & Rating Groups**.

The content tree displays the **Services & Rating Groups** group.

2. In the content tree, select the rating group from which you want to remove the service.

The work area displays information about the rating group.

3. Remove the service using one of the following methods:

- On the Rating Group Administration page, click the Remove icon, located to the right to the service you want to remove. The service is removed from the rating group immediately; there is no confirmation message.
- From the content tree, select the service in the rating group; the Service Administration page opens, displaying information about the service. Click **Delete**. A conformation message displays. Click **OK**.

The service is removed from the rating group.

Deleting a Rating Group

Deleting a rating group does not delete any services associated with the deleted group; services remain in the **Services & Rating Groups** group. You cannot delete the **Services & Rating Groups** group. You cannot delete a rating group that is referenced in a policy. Otherwise, to delete a rating group:

1. From the **Policy Server** section of the navigation pane, select **Services & Rating Groups**.

The content tree displays the **Services & Rating Groups** group.

2. From the content tree, select the rating group you want to delete.

The Rating Group Administration page opens in the work area, displaying the contents of the selected rating group.

3. Click **Delete**.

A confirmation message displays.

4. Click **OK**.

The rating group is deleted.

Managing Traffic Profiles

This chapter defines how to create and manage traffic profiles in the CMP system.

A traffic profile is a set of values defined for parameters that are used in protocol messages within an MPE device.

About Traffic Profiles

A traffic profile is a set of values defined for parameters that are used in protocol messages within the MPE device. Typically, these traffic profile values are used to define the Quality of Service (QoS) for sessions that are managed by those protocol messages. You can use traffic profiles to implement policy and charging control (PCC) rules.

Traffic profiles are used in the MPE device under several situations. For example:

- They define default settings for protocol messages (see the appropriate *CMP User's Guide*).
- They modify protocol messages, thus modifying the QoS for sessions managed by those messages (see [Creating a Policy Rule](#)).

A traffic profile can be applied by a policy rule trigger or by default if no policy rule is triggered.

Each traffic profile has a type associated with it. Since each protocol supports different parameters for controlling QoS settings, the available MPE parameters depend on the underlying protocol. Therefore, each profile type is associated with a single protocol, but a single protocol can support multiple profile types.

You can create multiple traffic profiles of the same type, as the values of the parameters for each profile determine the actual QoS that is associated with that profile. For example, one possible set of traffic profiles is as follows:

Default

Default predefined profile

P2P

Profile for peer-to-peer traffic

RATE_LIMIT_128K

profile to limit download rate to 128 Kbps

RATE_LIMIT_64K

Profile to limit download rate to 64 Kbps

To manage traffic profiles, see:

- [Creating a Wireless Traffic Profile](#)
- [Creating a Cable Traffic Profile](#)
- [Modifying a Traffic Profile](#)

- [Deleting a Traffic Profile](#)

About Traffic Profile Variables

You can configure individual fields in a traffic profile as variables. Traffic profile variables are evaluated when the policy executes the traffic profile that contains it. Traffic profile variables let you reuse traffic profiles for a range of situations without having to create additional profiles that might differ only in a few ways, or add traffic profiles to policy tables. Traffic profile variables are available for the following profile types:

- ADC Rule
- Diameter QoS
- PCC Profile
- PCC Rule

To use variables in a traffic profile, select the **Enable Dynamic Override** check box when creating or editing the profile. This displays fields in which you can enter variables for one or more profile values.

A variable supersedes any defined static value. If a variable is not available when it is evaluated, the static value is used and the existing traffic profiles continue to work as before. If neither a variable nor a static value is available, the parameter is ignored and the associated AVP is not included under the Charging-Rule-Definition AVP.

You can include the following classes of traffic profile variables:

Substitution variables

Predefined variables available during policy rule execution within an MPE device to allow for substitution of these variables for contextual information. For example, {Time} is replaced by the time value when a policy rule that references it is evaluated.

Policy table variables

Variables that reference a policy table column.

Policy evaluation variables

Variables that exist only for the lifetime of a policy evaluation cycle (that is, the process of evaluating all the policies for a single request or context).

Session state variables

State variables that have a value that is saved only while the session they are associated with is valid. After the session is terminated, session state variables no longer have a value and are no longer available for use in policies.

Subscriber local state variables

State variables that exist locally on the MPE device and have a value while the associated subscriber has at least one session on that device. After the last session is terminated, subscriber local state variables no longer have a value and are no longer available for use in policies.

Subscriber remote state variables

State variables that exist remotely in an SPR database and have a value while the associated subscriber exists in that database. Using subscriber remote state variables requires that an SPR or HSS database is configured and capable of storing these variables.

See [Example Traffic Profile Variables](#) for examples of traffic profile variables.

Example Traffic Profile Variables

The examples provided in this section represent each class of traffic profile variables:

Substitution Variable

`{Session.APNAggregateMaxBitrateUplink}`

Replaced with the `APNAggregateMaxBitrateUplink` value currently saved in the session.

Policy Table Variable

`{PolicyTable.pccrule.GuaranteedBitrateUplink}`

The policy table named `pccrule` is evaluated by looking at the `GuaranteedBitrateUplink` column in this table.

Policy Evaluation Variable

`{Policy.Variable.Uplink}`

Replaced with the value of the policy variable named `Uplink` retrieved from the current policy evaluation cycle.

Session State Variable

`{Session.State.Uplink}`

Replaced with the value of the state variable named `Uplink` retrieved from the session.

Subscriber Local State Variable

`{User.LocalState.Uplink}`

Replaced with the value of the state variable named `Uplink` retrieved from the local user object on the MPE device.

Subscriber Remote State Variable

`{User.State.Uplink}`

Replaced with the value of the state variable named `Uplink` retrieved from the SPR database.

Creating a Wireless Traffic Profile

To create a traffic profile in Wireless mode:

1. From the **Policy Server** section of the navigation pane, select **Traffic Profiles**.

The content tree displays a list of traffic profile group; the initial group is **ALL**.

2. Select the **Traffic Profiles** group.

The Traffic Profile Administration page opens in the work area and lists available traffic profiles.

3. Click **Create Traffic Profile**.

The New Traffic Profile page opens.

4. Enter the **Name** for the traffic profile.

The name can only contain the characters A–Z, a–z, 0–9, period (.), hyphen (-), and underline (_). The maximum length is 255 characters.

5. Select the **Traffic Profile Type** from the list.

The types of traffic profiles available depend on the mode in which the CMP system is operating. Wireless Mode contains the following traffic profile types:

- **ADC Rule** (default) — an application detection control rule.
- **Diameter QoS** — a policy and charging control rule.
- **PCC Profile** — a policy and charging control profile.
- **PCC Rule** — a policy and charging control rule.
- **PCC Rule Extension** — a policy and charging control rule extension.

 Note:

PCC Extensions mode must be enabled to see this profile type.

- **Predefined ADC Rule** — a predefined ADC rule residing on the PCEF.
- **Predefined ADC Rule Base** — a predefined group of ADC rules residing on the PCEF.
- **Predefined PCC Rule** — a predefined PCC rule residing on the PCEF.
- **Predefined PCC Rule Base** — a predefined group of PCC rules residing on the PCEF.
- **Service Control Engine (SCE) Profile** — a predefined policy on the SCE.

 Note:

SCE-Gx mode must be enabled to see this profile type.

6. Select to **Enable Dynamic Override** (available for ADC Rule, Diameter QoS, PCC Profile, and PCC Rule profiles).

If you select this option, **Dynamic Value** fields appear enabling you to enter configuration parameters. You can enter variables for the configuration parameters. Variable names must be enclosed in curly braces ({}). For more information about dynamic overrides, see [About Traffic Profile Variables](#).

7. Enter the parameters for the selected **Traffic Profile Type**.

For example, in Wireless mode, if you choose **Diameter QoS** as the **Traffic Profile Type**, the page displays the fields described in [Diameter QoS Traffic Profile Configuration Parameters](#).

The following list details the configuration parameters for traffic profile types:

- [ADC Rule Traffic Profile Configuration Parameters](#)
- [Diameter QoS Traffic Profile Configuration Parameters](#)
- [PCC Profile Traffic Profile Configuration Parameters](#)
- [PCC Rule Traffic Profile Configuration Parameters](#)

- [Predefined PCC Rule Extension Traffic Profile Configuration Parameters](#)
- [Predefined ADC Rule Traffic Profile Configuration Parameters](#)
- [Predefined ADC Rule Base Traffic Profile Configuration Parameters](#)
- [Predefined PCC Rule Traffic Profile Configuration Parameters](#)
- [Predefined PCC Rule Base Traffic Profile Configuration Parameters](#)
- [SCE Profile Traffic Profile Configuration Parameters](#)

8. Click **Save**.

The traffic profile is defined in the CMP database and can now be used in a policy.

ADC Rule Traffic Profile Configuration Parameters

Rule Name

Uniquely identifies the ADC rule. Used to reference an ADC rule in communication between the MPE device and a PCEF within one IP-CAN session.

Uplink Max Authorized Rate (bps)

Maximum authorized bandwidth in bits per second for uplinks (user equipment to network). Refer to [QoS Values for Traffic Profiles](#) for more information about bandwidths.

Downlink Max Authorized Rate (bps)

Maximum authorized bandwidth in bits per second for downlinks (network to user equipment). Refer to [QoS Values for Traffic Profiles](#) for more information about bandwidths.

Monitoring Key

Select a monitoring key that may apply to the ADC rule. For more information on monitoring keys, see [Managing Monitoring Keys](#).

The default is **N/A**.

Flow Status

Indicates whether the application traffic is enabled or disabled in either the uplink or downlink direction. Select from the following:

- **N/A** (default)
- **ENABLED_UPLINK**
- **ENABLED_DOWNLINK**
- **ENABLED**
- **DISABLED**

TDF Application Identifier

Identifies the traffic that belongs to the application to which the rule applies.

TDF Redirect Support

Indicates whether the application traffic should be redirected to another controlled address. Select from the following:

- **N/A** (default)
- **REDIRECTION_DISABLED**

- **REDIRECTION_ENABLED**

TDF Redirect Address Type

Specifies the format for the redirect address. Select from the following:

- **N/A** (default)
- **IPv4**
- **IPv6**
- **URL**
- **SIP_URI**

TDF Redirect Server Address

The address of the TDF redirect server in the specified address type.

Mute Notification

Used to disable application detection notifications from the TDF device. Select from the following:

- **N/A** (default)
- **MUTE_REQUIRED**

Service Identifier

Credit-control service identifier associated with the traffic defined by this rule. Only applicable if online charging is enabled.

Rating Group

Credit-control rating group associated with the traffic defined by this profile. Only applicable if online charging is enabled.

Reporting Level

Select from the following:

- **N/A** (default)
- **SERVICE_IDENTIFIER_LEVEL**
- **RATING_GROUP_LEVEL**

Online Charging

Specifies whether or not online charging is enabled in this profile. Select from the following:

- **N/A** (default)
- **DISABLE_ONLINE**
- **ENABLE_ONLINE**

Offline Charging

Specifies whether or not offline charging is enabled in this profile. Select from the following:

- **N/A** (default)
- **DISABLE_OFFLINE**
- **ENABLE_OFFLINE**

Metering Method

Defines how service data-flow traffic is metered for offline charging. Select from the following:

- **N/A** (default)
- **DURATION**
- **VOLUME**
- **DURATION_VOLUME**
- **EVENT**

**Note:**

Event-based charging is only applicable to predefined PCC rules using a service data-flow filter and any PCC rule (predefined and dynamic) using an application detection identifier.

Precedence

Precedence value of the profile. The lower the precedence, the higher the priority.

Diameter QoS Traffic Profile Configuration Parameters

QoS Class Identifier

Identifies the QoS class. Enter a value between 1 and 254 or select from the following:

- **N/A** (default)
- **1 = Conversational speech**
- **2 = Conversational**
- **3 = Streaming speech**
- **4 = Streaming**
- **5 = Interactive with priority 1 signalling**
- **6 = Interactive with priority 1**
- **7 = Interactive with priority 2**
- **8 = Interactive with priority 3**
- **9 = Background**
- **65 = MC-PTT Voice**
- **66 = PTT Voice**
- **69 = MC-PTT Signaling**
- **70 = MC Data**

**Note:**

QCI values between 1 and 254 are supported. Values other than 1 through 9, 65, 66, 69, and 70 are undefined.

Uplink Max Authorized Rate (bps)

Maximum authorized bandwidth in bits per second for uplinks (user equipment to network). Refer to [QoS Values for Traffic Profiles](#) for more information about bandwidths.

Downlink Max Authorized Rate (bps)

Maximum authorized bandwidth in bits per second for downlinks (network to user equipment). Refer to [QoS Values for Traffic Profiles](#) for more information about bandwidths.

Uplink Min Guaranteed Rate (bps)

Minimum guaranteed bandwidth in bits per second for uplinks (user equipment to network). Only applicable if the QoS class identifier is between 1 and 4. Refer to [QoS Values for Traffic Profiles](#) for more information about bandwidths.

Downlink Min Guaranteed Rate (bps)

Minimum guaranteed bandwidth in bits per second for downlinks (network to user equipment). Only applicable if the QoS class identifier is between 1 and 4. Refer to [QoS Values for Traffic Profiles](#) for more information about bandwidths.

ARP Priority Level

Allocation and Retention Priority level of the service flows associated with this Diameter profile. Specify 1 (highest) to 15 (lowest).

ARP Preemption Capability

Select from the following:

- **N/A** (default)
- **PREEMPTION_CAPABILITY_ENABLED**
- **PREEMPTION_CAPABILITY_DISABLED**

ARP Preemption Vulnerability

Select from the following:

- **N/A** (default)
- **PREEMPTION_VULNERABILITY_ENABLED**
- **PREEMPTION_VULNERABILITY_DISABLED**

Resource Allocation Notification

Indicates that the allocation of resources for the related PCC rules are confirmed. Select from the following:

- **N/A** (default)
- **ENABLE_NOTIFICATION**

PCC Profile Traffic Profile Configuration Parameters

QoS Class Identifier

Identifies the QoS class. Enter a value between 1 and 254 or select from the following:

- **N/A** (default)
- **1 = Conversational speech**
- **2 = Conversational**
- **3 = Streaming speech**
- **4 = Streaming**
- **5 = Interactive with priority 1 signalling**
- **6 = Interactive with priority 1**
- **7 = Interactive with priority 2**
- **8 = Interactive with priority 3**
- **9 = Background**
- **65 = MC-PTT Voice**
- **66 = PTT Voice**
- **69 = MC-PTT Signaling**
- **70 = MC Data**



Note:

QCI values between 1 and 254 are supported. Values other than 1 through 9, 65, 66, 69, and 70 are undefined.

Uplink Max Authorized Rate (bps)

Maximum authorized bandwidth in bits per second for uplinks (user equipment to network). Refer to [QoS Values for Traffic Profiles](#) for more information about bandwidths.

Downlink Max Authorized Rate (bps)

Maximum authorized bandwidth in bits per second for downlinks (network to user equipment). Refer to [QoS Values for Traffic Profiles](#) for more information about bandwidths.

Uplink Min Guaranteed Rate (bps)

Minimum guaranteed bandwidth in bits per second for uplinks (user equipment to network). Only applicable if the QoS class identifier is between 1 and 4. Refer to [QoS Values for Traffic Profiles](#) for more information about bandwidths.

Downlink Min Guaranteed Rate (bps)

Minimum guaranteed bandwidth in bits per second for downlinks (network to user equipment). Only applicable if the QoS class identifier is between 1 and 4. Refer to [QoS Values for Traffic Profiles](#) for more information about bandwidths.

ARP Priority Level

Allocation and Retention Priority level of the service flows associated with this Diameter profile. Specify 1 (highest) to 15 (lowest).

ARP Preemption Capability

Select from the following:

- **N/A** (default)
- **PREEMPTION_CAPABILITY_ENABLED**
- **PREEMPTION_CAPABILITY_DISABLED**

ARP Preemption Vulnerability

Select from the following:

- **N/A** (default)
- **PREEMPTION_VULNERABILITY_ENABLED**
- **PREEMPTION_VULNERABILITY_DISABLED**

Monitoring Key

Select a monitoring key that may apply to the PCC profile. For more information on monitoring keys, see [Managing Monitoring Keys](#). The default is **N/A**.

Service Identifier

Credit-control service identifier associated with the traffic defined by this rule. Only applicable if online charging is enabled.

Rating Group

Credit-control rating group associated with the traffic defined by this profile. Only applicable if online charging is enabled.

Reporting Level

Select from the following:

- **N/A** (default)
- **SERVICE_IDENTIFIER_LEVEL**
- **RATING_GROUP_LEVEL**
- **SPONSORED_CONNECTIVITY_LEVEL**

Online Charging

Specifies whether or not online charging is enabled in this profile. Select from the following:

- **N/A** (default)
- **DISABLE_ONLINE**
- **ENABLE_ONLINE**

Offline Charging

Specifies whether or not offline charging is enabled in this profile. Select from the following:

- **N/A** (default)
- **DISABLE_OFFLINE**

- **ENABLE_OFFLINE**

Metering Method

Defines how service data-flow traffic is metered for offline charging. Select from the following:

- **N/A** (default)
- **DURATION**
- **VOLUME**
- **DURATION_VOLUME**
- **EVENT**

**Note:**

Event-based charging is only applicable to predefined PCC rules using a service data-flow filter and any PCC rule (predefined and dynamic) using an application detection identifier.

Flow Status

Select from the following:

- **N/A** (default)
- **ENABLED_UPLINK**
- **ENABLED_DOWNLINK**
- **ENABLED**
- **DISABLED**

Precedence

Precedence value of the profile. The lower the precedence, the higher the priority.

Resource Allocation Notification

Indicates that the allocation of resources for the related PCC rules are confirmed. Select from the following:

- **N/A** (default)
- **ENABLE_NOTIFICATION**

Required Access Info

Select from the following:

- **N/A** (default)
- **USER_LOCATION** — the subscriber's location
- **MS_TIME_ZONE** — the mobile subscriber's time zone
- **USER_LOCATION and MS_TIME_ZONE** — the (mobile) subscriber's location and time zone

If this field is not set, the device uses the values sent in AF requests; otherwise, it uses the values set here.

Sponsor Identity

Name identifying a connectivity sponsor.

Application Service Provider Identity

Name identifying an application service provider.

Flow Descriptions

IP flows associated with this profile. A comma-separated list of Diameter IP Filter rules following the format specified in RFC 3588 section 4.3. Used in the following cases:

- An old traffic profile is imported, and the flow description is not an empty string.
- An upgrade from an older version is in process and the existing traffic profile flow description is not an empty string.

For all other cases, the **Use Flow Informations** fields indicate the IP flows.

Use Flow Informations

IP flow description, TOS traffic class, TOS traffic class mask, and flow direction information associated with the profile. Multiple Flow Informations can be added to the same traffic profile. This field is used instead of the **Flow Descriptions** field.

**Note:**

If the **Flow Descriptions** field is populated, then the **Use Flow Informations** field cannot be used.

Click **Add** next to the **Use Flow Informations** field to access the Flow Information fields. Double-click each column to edit the values in the column. Click **Del** next to an existing Flow Information row to delete the row.

Predefined PCC Rule Extension Traffic Profile Configuration Parameters

**Note:**

For the PCC Rule Profile Extension to be listed, you must have the Cisco Gx feature enabled.

Name

Name identifying the Predefined PCC Rule Extension. The name must not contain apostrophes (').

Volume Threshold

Enter a number between 1 and 9999999999.

Service Flow Detection Trigger

Select from the following:

- **N/A** (default)

- **ENABLE**
- **DISABLE**

Charging Rule Remove Trigger

Select from the following:

- **N/A** (default)
- **ENABLE**
- **DISABLE**

PCC Rule Traffic Profile Configuration Parameters

Rule Name

Name identifying the provisioned PCC rule. The name must not contain apostrophes (').

QoS Class Identifier

Identifies the QoS class. Enter a value between 1 and 254 or select from the following:

- **N/A** (default)
- **1 = Conversational speech**
- **2 = Conversational**
- **3 = Streaming speech**
- **4 = Streaming**
- **5 = Interactive with priority 1 signalling**
- **6 = Interactive with priority 1**
- **7 = Interactive with priority 2**
- **8 = Interactive with priority 3**
- **9 = Background**
- **65 = MC-PTT Voice**
- **66 = PTT Voice**
- **69 = MC-PTT Signaling**
- **70 = MC Data**

**Note:**

QCI values between 1 and 254 are supported. Values other than 1 through 9, 65, 66, 69, and 70 are undefined.

Uplink Max Authorized Rate (bps)

Maximum authorized bandwidth in bits per second for uplinks (user equipment to network). Refer to [QoS Values for Traffic Profiles](#) for more information about bandwidths.

Downlink Max Authorized Rate (bps)

Maximum authorized bandwidth in bits per second for downlinks (network to user equipment). Refer to [QoS Values for Traffic Profiles](#) for more information about bandwidths.

Uplink Min Guaranteed Rate (bps)

Minimum guaranteed bandwidth in bits per second for uplinks (user equipment to network). Only applicable if the QoS class identifier is between 1 and 4. Refer to [QoS Values for Traffic Profiles](#) for more information about bandwidths.

Downlink Min Guaranteed Rate (bps)

Minimum guaranteed bandwidth in bits per second for downlinks (network to user equipment). Only applicable if the QoS class identifier is between 1 and 4. Refer to [QoS Values for Traffic Profiles](#) for more information about bandwidths.

ARP Priority Level

Allocation and Retention Priority level of the service flows associated with this Diameter profile. Specify 1 (highest) to 15 (lowest).

ARP Preemption Capability

Select from the following:

- **N/A** (default)
- **PREEMPTION_CAPABILITY_ENABLED**
- **PREEMPTION_CAPABILITY_DISABLED**

ARP Preemption Vulnerability

Select from the following:

- **N/A** (default)
- **PREEMPTION_VULNERABILITY_ENABLED**
- **PREEMPTION_VULNERABILITY_DISABLED**

Service Identifier

Credit-control service identifier associated with the traffic defined by this rule. Only applicable if online charging is enabled.

Rating Group

Credit-control rating group associated with the traffic defined by this profile. Only applicable if online charging is enabled.

Monitoring Key

Select a monitoring key that may apply to the PCC profile. For more information on monitoring keys, see [Managing Monitoring Keys](#).

The default is **N/A**.

Reporting Level

Select from the following:

- **N/A** (default)
- **SERVICE_IDENTIFIER_LEVEL**
- **RATING_GROUP_LEVEL**
- **SPONSORED_CONNECTIVITY_LEVEL**

Online Charging

Specifies whether or not online charging is enabled in this profile. Select from the following:

- **N/A** (default)
- **DISABLE_ONLINE**
- **ENABLE_ONLINE**

Offline Charging

Specifies whether or not offline charging is enabled in this profile. Select from the following:

- **N/A** (default)
- **DISABLE_OFFLINE**
- **ENABLE_OFFLINE**

Metering Method

Defines how service data-flow traffic is metered for offline charging. Select from the following:

- **N/A** (default)
- **DURATION**
- **VOLUME**
- **DURATION_VOLUME**
- **EVENT**



Note:

Event-based charging is only applicable to predefined PCC rules using a service data-flow filter and any PCC rule (predefined and dynamic) using an application detection identifier.

Flow Status

Select from the following:

- **N/A** (default)
- **ENABLED_UPLINK**
- **ENABLED_DOWNLINK**
- **ENABLED**
- **DISABLED**

Precedence

Precedence value of the profile. The lower the precedence, the higher the priority.

Resource Allocation Notification

Indicates that the allocation of resources for the related PCC rules are confirmed. Select from the following:

- **N/A** (default)
- **ENABLE_NOTIFICATION**

Required Access Info

Select from the following:

- **N/A** (default)
- **USER_LOCATION** — the subscriber's location
- **MS_TIME_ZONE** — the mobile subscriber's time zone
- **USER_LOCATION and MS_TIME_ZONE** — the (mobile) subscriber's location and time zone

If this field is not set, the device uses the values sent in AF requests; otherwise, it uses the values set here.

TDF Application Identifier

Determines the traffic that belongs to the application.

TDF Redirect Support

Select from the following:

- **N/A** (default)
- **REDIRECTION_DISABLED**
- **REDIRECTION_ENABLED**

TDF Redirect Address Type

Select from the following:

- **N/A** (default)
- **IPv4**
- **IPv6**
- **URL**
- **SIP_URI**

TDF Redirect Server Address

The address of the TDF redirect server.

Mute Notification

Used to disable application detection notifications from the TDF device. Select from the following:

- **N/A** (default)
- **MUTE_REQUIRED**

Sponsor Identity

Name identifying a connectivity sponsor.

Application Service Provider Identity

Name identifying an application service provider.

PS to CS Session Continuity

Indicates that the service data flow carries video and allows for packet switch (PS) to circuit switch (CS) session continuity. Select from the following:

- **N/A** (default)
- **VIDEO_PS2CS_CONT_CANDIDATE**

Flow Descriptions

IP flows associated with this profile. A comma-separated list of Diameter IP Filter rules following the format specified in *RFC 3588 section 4.3*. Used in the following cases:

- An old traffic profile is imported, and the flow description is not an empty string.
- An upgrade from an older version is in process and the existing traffic profile flow description is not an empty string.

For all other cases, the **Use Flow Informations** fields indicate the IP flows.

Use Flow Informations

IP flow description, TOS traffic class, TOS traffic class mask, and flow direction information associated with the profile. Multiple Flow Informations can be added to the same traffic profile. This field is used instead of the **Flow Descriptions** field.

**Note:**

If the **Flow Descriptions** field is populated, then the **Use Flow Informations** field cannot be used.

To manage Flow Informations:

1. Click **Add** next to the **Use Flow Informations** field to access the Flow Information fields.
2. Double-click each column to edit the values in the column.
3. Click **Del** next to an existing Flow Information row to delete the row.

**Note:**

Variables are not available for this configuration parameter.

Predefined ADC Rule Traffic Profile Configuration Parameters

Rule Name

Name identifying the Predefined ADC Rule. The name must not contain apostrophes (').

Description

Description of the rule.

Predefined ADC Rule Base Traffic Profile Configuration Parameters

Rule Name

Name identifying the Predefined ADC Rule Base. The name must not contain apostrophes (').

Description

Description of the rule base.

Predefined PCC Rule Traffic Profile Configuration Parameters

Rule Name

Name identifying the Predefined PCC Rule. The name must not contain apostrophes (').

Description

Description of the rule.

Monitoring Key

Select **N/A** or the name of a monitoring key defined in the CMP database. See [Managing Monitoring Keys](#) for information on monitoring keys.

ServiceFlowDetection

Select from the following:

- **N/A** (default)
- **ENABLE_DETECTION**



Note:

For ServiceFlowDetection to be listed, you must have the PCC Extensions mode enabled.

Predefined PCC Rule Base Traffic Profile Configuration Parameters

Rule Base Name

Name identifying the Predefined PCC Rule Base. The name must not contain apostrophes (').

Description

Description of the rule base.

ServiceFlowDetection

Select from the following:

- **N/A** (default)
- **ENABLE_DETECTION**



Note:

For ServiceFlowDetection to be listed, you must have the PCC Extensions mode enabled.

SCE Profile Traffic Profile Configuration Parameters

**Note:**

For the SCE Profile to be listed, you must have the SCE-Gx feature enabled.

Name

Name identifying the SCE profile. The name must not contain apostrophes (').

Package ID

Identifier corresponding to a policy defined on the SCE.

Description

Description of the SCE profile.

QoS Values for Traffic Profiles

Table 33-1 lists the minimum and maximum bandwidth values available when defining a traffic profile type.

**Note:**

An ADC Rule only has Uplink Max Authorized rate and Downlink Max Authorized rate.

Table 33-1 Qos Values in Traffic Profile

Traffic Profile Type	Uplink Max Authorized Rate (bps)	Downlink Max Authorized Rate (bps)	Uplink Min Guaranteed Rate (bps)	Downlink Min Guaranteed Rate (bps)
Diameter Qos	$(2^{32} - 1) * 1000$	$(2^{32} - 1) * 1000$	$(2^{32} - 1) * 1000$	$(2^{32} - 1) * 1000$
PCC Profile	$(2^{32} - 1) * 1000$	$(2^{32} - 1) * 1000$	$(2^{32} - 1) * 1000$	$(2^{32} - 1) * 1000$
PCC Rule	$(2^{32} - 1) * 1000$	$(2^{32} - 1) * 1000$	$(2^{32} - 1) * 1000$	$(2^{32} - 1) * 1000$

Creating a Cable Traffic Profile

To create a traffic profile in Cable mode:

1. From the **Policy Server** section of the navigation pane, select **Traffic Profiles**.
The content tree displays a list of traffic profile group; the initial group is **ALL**.
2. Select the **Traffic Profiles** group.
The Traffic Profile Administration page opens in the work area and lists available traffic profiles.
3. Click **Create Traffic Profile**.
The New Traffic Profile page opens.

4. Enter the **Name** for the traffic profile.

The name can only contain the characters A–Z, a–z, 0–9, period (.), hyphen (-), and underline (_). The maximum length is 255 characters.

5. Select the **Traffic Profile Type** from the list.

The types of traffic profiles available depend on the mode in which the CMP system is operating. Cable Mode contains the following traffic profile types:

- **Best Effort** (default) — Transmission opportunities are granted on a first-come, first-served basis. Appropriate for upstream service flows such as Web browsing, e-mail, or instant messaging.
- **Diameter QoS** — a policy and charging control rule.
- **Downstream** — Defined through a similar set of QoS parameters that are associated with the best-effort scheduling type on upstream service flows. Appropriate for all downstream service flows.
- **Non-Real-Time Polling** — Cable modems are polled at a fixed interval for queued data. Appropriate for upstream service flows that require high throughput, and traffic that requires variable-sized data grants on a regular basis, such as high-bandwidth FTP.
- **RSVP Flow Spec** — Receivers initiate reservation requests for unidirectional data flows, and senders respond with path information.
- **Real-Time Polling** — Cable modems are polled at a fixed but short interval for queued data. Appropriate for upstream service flows of real-time traffic that generate variable-sized data packets on a periodic basis and have inflexible latency and throughput requirements, such as MPEG video.
- **Service Class** — The profile will use a service class that is configured on the CMTS.
- **Unsolicited Grant** — A fixed-size grant is offered to service flows at fixed intervals without additional polling or interaction. Appropriate for upstream service flows of real-time traffic that generate fixed-size data packets on a periodic basis, such as VoIP.
- **Unsolicited Grant with Activity Detection** — When there is activity, the CMTS sends unsolicited fixed grants at fixed intervals to the cable modem. When there is no activity, the CMTS sends unicast poll requests to the cable modem to conserve unused bandwidth. Appropriate for upstream service flows that include silence suppression.

6. Select to **Enable Dynamic Override** (available for Diameter QoS profiles).

If you select this option, **Dynamic Value** fields are displayed for configuration parameters. You can enter variables for the configuration parameters. Variable names must be enclosed in curly braces ({}). For more information about dynamic overrides, see [About Traffic Profile Variables](#).

7. Enter the parameters for the selected **Traffic Profile Type**.

The set of fields displayed on the Traffic Profile page varies depending on the **Traffic Profile Type** you select.

The following list details the configuration parameters for traffic profile types:

- [Best Effort Traffic Profile Configuration Parameters](#)
- [Diameter QoS Traffic Profile Configuration Parameters](#)

- [Downstream Traffic Profile Configuration Parameters](#)
- [Non-Real-Time Polling Traffic Profile Configuration Parameters](#)
- [RSVP Flow Spec Traffic Profile Configuration Parameters](#)
- [Real-Time Polling Traffic Profile Configuration Parameters](#)
- [Unsolicited Grant Traffic Profile Configuration Parameters](#)
- [Unsolicited Grant with Activity Detection Traffic Profile Configuration Parameters](#)

8. Click **Save**.

The traffic profile is defined in the CMP database and can now be used in a policy.

Best Effort Traffic Profile Configuration Parameters

Traffic Priority

Priority for the service flow. Higher-priority service flows are given preference over lower-priority service flows.

Request Transmission Policy

The interval usage code that the cable modem uses for upstream transmission requests and packet transmissions for this service flow. It also specifies whether requests can be piggybacked with data.

Max Sustained Traffic Rate (bps)

The maximum sustained rate, in bits per second, at which traffic can operate over the service flow.

Max Traffic Burst

The maximum burst size for the service flow.

Min Reserved Traffic Rate (bps)

The guaranteed minimum rate, in bits per second, that is reserved for the service flow.

Assumed Min Packet Size (bytes)

The assumed minimum packet size, in bytes, for which the minimum reserved traffic rate is provided.

Maximum Concatenated Bursts (bytes)

The maximum size, in bytes, of a concatenated frame (a group of frames) that a service flow can transmit.

Upstream Peak Traffic Rate

A four-byte unsigned integer field that specifies the peak traffic rate, in bits per second, that is allowed for a service flow. The range is 0 – 4,294,967,295 bps (4 Gbps–1).

Required Attribute Mask

A 32-bit mask that specifies whether certain attributes are required in a service flow.

Forbidden Attribute Mask

A 32-bit mask that specifies whether certain attributes are forbidden in a service flow.

Attribute Aggregation Rule Mask

A 32-bit mask that controls whether groups of attributes are either required or forbidden in a service flow.

Minimum Buffer

The lower limit for the size, in bits, of the buffer to be provided for a service flow. The range is 0 – 4,294,967,295 bits (4 Gb–1). The default is a value of 0, which indicates that there is no lower limit.

Target Buffer

The value for the size, in bits, of the buffer to be provided for a service flow. The range is 0 – 4,294,967,295 bits (4 Gb–1). If the parameter is omitted or set to a value of 0, then the device selects any buffer size within the range of the minimum and maximum buffers, using a vendor-specific algorithm.

Maximum Buffer

The upper limit for the size of the buffer to be provided for a service flow. The range is 0 – 4,294,967,295 bits (4 Gb–1). The default is no limit.

Diameter QoS Traffic Profile Configuration Parameters

QoS Class Identifier

Identifies the QoS class. Enter a value between 1 and 254 or select from the following:

- **N/A** (default)
- **1 = Conversational speech**
- **2 = Conversational**
- **3 = Streaming speech**
- **4 = Streaming**
- **5 = Interactive with priority 1 signalling**
- **6 = Interactive with priority 1**
- **7 = Interactive with priority 2**
- **8 = Interactive with priority 3**
- **9 = Background**
- **65 = MC-PTT Voice**
- **66 = PTT Voice**
- **69 = MC-PTT Signaling**
- **70 = MC Data**

**Note:**

QCI values between 1 and 254 are supported. Values other than 1 through 9, 65, 66, 69, and 70 are undefined.

Uplink Max Authorized Rate (bps)

Maximum authorized bandwidth in bits per second for uplinks (user equipment to network). Refer to [QoS Values for Traffic Profiles](#) for more information about bandwidths.

Downlink Max Authorized Rate (bps)

Maximum authorized bandwidth in bits per second for downlinks (network to user equipment). Refer to [QoS Values for Traffic Profiles](#) for more information about bandwidths.

Uplink Min Guaranteed Rate (bps)

Minimum guaranteed bandwidth in bits per second for uplinks (user equipment to network). Only applicable if the QoS class identifier is between 1 and 4. Refer to [QoS Values for Traffic Profiles](#) for more information about bandwidths.

Downlink Min Guaranteed Rate (bps)

Minimum guaranteed bandwidth in bits per second for downlinks (network to user equipment). Only applicable if the QoS class identifier is between 1 and 4. Refer to [QoS Values for Traffic Profiles](#) for more information about bandwidths.

ARP Priority Level

Allocation and Retention Priority level of the service flows associated with this Diameter profile. Specify 1 (highest) to 15 (lowest).

ARP Preemption Capability

Select from the following:

- **N/A** (default)
- **PREEMPTION_CAPABILITY_ENABLED**
- **PREEMPTION_CAPABILITY_DISABLED**

ARP Preemption Vulnerability

Select from the following:

- **N/A** (default)
- **PREEMPTION_VULNERABILITY_ENABLED**
- **PREEMPTION_VULNERABILITY_DISABLED**

Resource Allocation Notification

Indicates that the allocation of resources for the related PCC rules are confirmed. Select from the following:

- **N/A** (default)
- **ENABLE_NOTIFICATION**

Downstream Traffic Profile Configuration Parameters

Traffic Priority

Priority for the service flow. Higher-priority service flows are given preference over lower-priority service flows.

Downstream Resequencing

A 1-byte unsigned integer specifying the use of sequencing numbers in downstream service flows to allow the cable modem to re-order out of sequence packets. The cable modem will hold higher numbered packets while waiting for lower numbered packets to arrive.

**Note:**

Applications that can tolerate lost packets or applications that cannot tolerate packet latency of up to 18 milliseconds can disable the use of sequence numbers by setting the **Downstream Resequencing** value to 1.

Max Sustained Traffic Rate (bps)

The maximum sustained rate, in bits per second, at which traffic can operate over the service flow.

Max Traffic Burst

The maximum burst size for the service flow.

Min Reserved Traffic Rate (bps)

The guaranteed minimum rate, in bits per second, that is reserved for the service flow.

Assumed Min Packet Size (bytes)

The assumed minimum packet size, in bytes, for which the minimum reserved traffic rate is provided.

Max Downstream Latency

The maximum latency for downstream service flows.

Downstream Peak Traffic Rate

A four-byte unsigned integer field, specifying the rate parameter P of a token-bucket based peak rate limiter for packets of a downstream service flow. This lets you define a **Max Traffic Burst** value for the **Max Sustained Traffic Rate** much larger than a maximum packet size, but still limit the burst of packets consecutively transmitted for a service flow.

Required Attribute Mask

A 32-bit mask that specifies whether certain attributes are required in a service flow.

Forbidden Attribute Mask

A 32-bit mask that specifies whether certain attributes are forbidden in a service flow.

Attribute Aggregation Rule Mask

A 32-bit mask that controls whether groups of attributes are either required or forbidden in a service flow.

Minimum Buffer

The lower limit for the size, in bits, of the buffer to be provided for a service flow. The range is 0 – 4,294,967,295 bits (4 Gb–1). The default is a value of 0, which indicates that there is no lower limit.

Target Buffer

The value for the size, in bits, of the buffer to be provided for a service flow. The range is 0 – 4,294,967,295 bits (4 Gb–1). If the parameter is omitted or set to a value of 0, then the device selects any buffer size within the range of the minimum and maximum buffers, using a vendor-specific algorithm.

Maximum Buffer

The upper limit for the size of the buffer to be provided for a service flow. The range is 0 – 4,294,967,295 bits (4 Gb–1). The default is no limit.

Non-Real-Time Polling Traffic Profile Configuration Parameters

Traffic Priority

Priority for the service flow. Higher-priority service flows are given preference over lower-priority service flows.

Request Transmission Policy

The interval usage code that the cable modem uses for upstream transmission requests and packet transmissions for this service flow. It also specifies whether requests can be piggybacked with data.

Max Sustained Traffic Rate (bps)

The maximum sustained rate, in bits per second, at which traffic can operate over the service flow.

Max Traffic Burst

The maximum burst size for the service flow.

Min Reserved Traffic Rate (bps)

The guaranteed minimum rate, in bits per second, that is reserved for the service flow.

Assumed Min Packet Size (bytes)

The assumed minimum packet size, in bytes, for which the minimum reserved traffic rate is provided.

Nominal Polling Interval (microsec)

The nominal interval, in microseconds, between successive unicast request opportunities for this service flow.

Maximum Concatenated Bursts (bytes)

The largest transmission of concatenated frames, in bytes, that a modem can make on behalf of the service flow.

Upstream Peak Traffic Rate

A four-byte unsigned integer field that specifies the peak traffic rate, in bits per second, that is allowed for a service flow. The range is 0 – 4,294,967,295 bps (4 Gbps–1).

Required Attribute Mask

A 32-bit mask that specifies whether certain attributes are required in a service flow.

Forbidden Attribute Mask

A 32-bit mask that specifies whether certain attributes are forbidden in a service flow.

Attribute Aggregation Rule Mask

A 32-bit mask that controls whether groups of attributes are either required or forbidden in a service flow.

Minimum Buffer

The lower limit for the size, in bits, of the buffer to be provided for a service flow. The range is 0 – 4,294,967,295 bits (4 Gb–1). The default is a value of 0, which indicates that there is no lower limit.

Target Buffer

The value for the size, in bits, of the buffer to be provided for a service flow. The range is 0 – 4,294,967,295 bits (4 Gb–1). If the parameter is omitted or set to a value of 0, then the

device selects any buffer size within the range of the minimum and maximum buffers, using a vendor-specific algorithm.

Maximum Buffer

The upper limit for the size of the buffer to be provided for a service flow. The range is 0 – 4,294,967,295 bits (4 Gb–1). The default is no limit.

RSVP Flow Spec Traffic Profile Configuration Parameters

Service Number

Select from the following:

- **N/A** (default)
- **2 = Guaranteed Service** — controls the maximum delay and ensures no packet loss
- **5 = Controlled Load Service** — appropriate for soft QoS applications

Token Bucket Rate (bytes/sec)

Defines how traffic will be injected into the inter network by the sending application.

Token Bucket Size (bytes)

The maximum amount of data that the flow can send at the peak rate.

Peak Data Rate (bytes/sec)

The peak data rate of bytes of data transmitted per second at peak times.

Minimum Policed Unit (bytes)

The minimum policed unit of a packet that can be subject to policing.

Maximum Packet Size (bytes)

The maximum packet size of a burst of data that can exceed the given bandwidth limit

Rate (bytes/sec)

The rate in bytes per second at which data is transmitted.

Slack Term (microsec)

The slack term due to latency or jitter depending on the service.

Real-Time Polling Traffic Profile Configuration Parameters

Request Transmission Policy

The interval usage code that the cable modem uses for upstream transmission requests and packet transmissions for this service flow. It also specifies whether requests can be piggybacked with data.

Max Sustained Traffic Rate (bps)

The maximum sustained rate, in bits per second, at which traffic can operate over the service flow.

Max Traffic Burst

The maximum burst size for the service flow.

Min Reserved Traffic Rate (bps)

The guaranteed minimum rate, in bits per second, that is reserved for the service flow.

Assumed Min Packet Size (bytes)

The assumed minimum packet size, in bytes, for which the minimum reserved traffic rate is provided.

Nominal Polling Interval (microsec)

The nominal interval, in microseconds, between successive unicast request opportunities for this service flow.

Tolerated Poll Jitter (microsec)

The maximum amount of time, in microseconds, that unicast request intervals can be delayed beyond the nominal polling interval.

Maximum Concatenated Bursts (bytes)

The maximum size, in bytes, of a concatenated frame (a group of frames) that a service flow can transmit.

Upstream Peak Traffic Rate

A four-byte unsigned integer field that specifies the peak traffic rate, in bits per second, that is allowed for a service flow. The range is 0 – 4,294,967,295 bps (4 Gbps–1).

Required Attribute Mask

A 32-bit mask that specifies whether certain attributes are required in a service flow.

Forbidden Attribute Mask

A 32-bit mask that specifies whether certain attributes are forbidden in a service flow.

Attribute Aggregation Rule Mask

A 32-bit mask that controls whether groups of attributes are either required or forbidden in a service flow.

Minimum Buffer

The lower limit for the size, in bits, of the buffer to be provided for a service flow. The range is 0 – 4,294,967,295 bits (4 Gb–1). The default is a value of 0, which indicates that there is no lower limit.

Target Buffer

The value for the size, in bits, of the buffer to be provided for a service flow. The range is 0 – 4,294,967,295 bits (4 Gb–1). If the parameter is omitted or set to a value of 0, then the device selects any buffer size within the range of the minimum and maximum buffers, using a vendor-specific algorithm.

Maximum Buffer

The upper limit for the size of the buffer to be provided for a service flow. The range is 0 – 4,294,967,295 bits (4 Gb–1). The default is no limit.

Unsolicited Grant Traffic Profile Configuration Parameters

Request Transmission Policy

The interval usage code that the cable modem uses for upstream transmission requests and packet transmissions for this service flow. It also specifies whether requests can be piggybacked with data.

Unsolicited Grant Size (bytes)

The size, in bytes, of the individual data grants provided to the service flow.

Grants Per Interval

The actual number of data grants given to the service flow during each nominal grant interval.

Nominal Grant Interval

The nominal interval between successive unsolicited data grant opportunities for this service flow.

Tolerated Grant Jitter (microsec)

The maximum amount of time, in microseconds, that the transmission opportunities can be delayed beyond the nominal grant interval.

Upstream Peak Traffic Rate

A four-byte unsigned integer field that specifies the peak traffic rate, in bits per second, that is allowed for a service flow. The range is 0 – 4,294,967,295 bps (4 Gbps–1).

Required Attribute Mask

A 32-bit mask that specifies whether certain attributes are required in a service flow.

Forbidden Attribute Mask

A 32-bit mask that specifies whether certain attributes are forbidden in a service flow.

Attribute Aggregation Rule Mask

A 32-bit mask that controls whether groups of attributes are either required or forbidden in a service flow.

Minimum Buffer

The lower limit for the size, in bits, of the buffer to be provided for a service flow. The range is 0 – 4,294,967,295 bits (4 Gb–1). The default is a value of 0, which indicates that there is no lower limit.

Target Buffer

The value for the size, in bits, of the buffer to be provided for a service flow. The range is 0 – 4,294,967,295 bits (4 Gb–1). If the parameter is omitted or set to a value of 0, then the device selects any buffer size within the range of the minimum and maximum buffers, using a vendor-specific algorithm.

Maximum Buffer

The upper limit for the size of the buffer to be provided for a service flow. The range is 0 – 4,294,967,295 bits (4 Gb–1). The default is no limit.

Unsolicited Grant with Activity Detection Traffic Profile Configuration Parameters

Request Transmission Policy

The interval usage code that the cable modem uses for upstream transmission requests and packet transmissions for this service flow. It also specifies whether requests can be piggybacked with data.

Unsolicited Grant Size (bytes)

The size, in bytes, of the individual data grants provided to the service flow.

Grants Per Interval

The actual number of data grants given to the service flow during each nominal grant interval.

Nominal Grant Interval

The nominal interval between successive unsolicited data grant opportunities for this service flow.

Tolerated Grant Jitter (microsec)

The maximum amount of time, in microseconds, that the transmission opportunities can be delayed beyond the nominal grant interval.

Nominal Polling Interval (microsec)

The nominal interval, in microseconds, between successive unicast request opportunities for this service flow.

Tolerated Poll Jitter (microsec)

The maximum amount of time, in microseconds, that unicast request intervals can be delayed beyond the nominal polling interval.

Upstream Peak Traffic Rate

A four-byte unsigned integer field that specifies the peak traffic rate, in bits per second, that is allowed for a service flow. The range is 0 – 4,294,967,295 bps (4 Gbps–1).

Required Attribute Mask

A 32-bit mask that specifies whether certain attributes are required in a service flow.

Forbidden Attribute Mask

A 32-bit mask that specifies whether certain attributes are forbidden in a service flow.

Attribute Aggregation Rule Mask

A 32-bit mask that controls whether groups of attributes are either required or forbidden in a service flow.

Minimum Buffer

The lower limit for the size, in bits, of the buffer to be provided for a service flow. The range is 0 – 4,294,967,295 bits (4 Gb–1). The default is a value of 0, which indicates that there is no lower limit.

Target Buffer

The value for the size, in bits, of the buffer to be provided for a service flow. The range is 0 – 4,294,967,295 bits (4 Gb–1). If the parameter is omitted or set to a value of 0, then the device selects any buffer size within the range of the minimum and maximum buffers, using a vendor-specific algorithm.

Maximum Buffer

The upper limit for the size of the buffer to be provided for a service flow. The range is 0 – 4,294,967,295 bits (4 Gb–1). The default is no limit.

Deploying a Traffic Profile

To deploy a traffic profile to an MPE device:

1. From the **Policy Server** section of the navigation pane, select **Configuration**.
The content tree displays a list of server groups; the initial group is **ALL**.
2. From the content tree, select the MPE device.

The Policy Server Administration page opens.

3. Select the **Policy Server** tab.

The page shows the current configuration for the selected device.

4. Click **Modify**.

The Modify Policy Server page opens.

5. In the **Diameter** section, select the **Diameter PCEF Default Profile** from the list.

The list includes all the traffic profiles defined in the CMP system.

6. Click **Save**.

The traffic profile is deployed to the specified device.

Modifying a Traffic Profile

To modify a traffic profile:

1. From the **Policy Server** section of the navigation pane, select **Traffic Profiles**.

The content tree displays a list of traffic profile group; the initial group is **ALL**.

2. Select the **Traffic Profiles** group.

The Traffic Profile Administration page opens in the work area and lists available traffic profiles.

3. Select the profile you want to modify.

Profile information is displayed.

4. Click **Modify**.

The Modify Traffic Profile page opens.

5. Modify profile information as required.

For a description of the fields contained on this page, see the traffic profile section for your mode:

- [Creating a Wireless Traffic Profile](#)
- [Creating a Cable Traffic Profile](#)

6. Click **Save**.

The traffic profile is modified.

Deleting a Traffic Profile



Note:

You cannot delete a traffic profile that is included in a policy or is deployed on an MPE device.

To delete a traffic profile:

1. From the **Policy Server** section of the navigation pane, select **Traffic Profiles**.

The content tree displays a list of traffic profile group; the initial group is **ALL**.

2. Select the **Traffic Profiles** group.

The Traffic Profile Administration page opens in the work area and lists available traffic profiles.

3. Delete the traffic profile using one of the following methods:

- From the work area, click  (trash can icon), located to the right of the traffic profile.
- From the content tree, select the traffic profile and click **Delete**.

A confirmation message displays.

4. Click **OK** to delete the traffic profile.

The traffic profile is deleted.

About Traffic Profile Groups

For organizational purposes, you can aggregate traffic profiles into groups. After a traffic profile group is created, it can be populated with individual traffic profiles.

This section describes how to manage traffic profile groups:

- [Creating a Traffic Profile Group](#)
- [Creating a Wireless Traffic Profile](#)
- [Modifying a Traffic Profile Group](#)
- [Removing a Traffic Profile from a Traffic Profile Group](#)
- [Deleting a Traffic Profile Group](#)

Creating a Traffic Profile Group

To create a traffic profile group:

1. From the **Policy Server** section of the navigation pane, select **Traffic Profiles**.

The content tree displays a list of traffic profile group; the initial group is **ALL**.

2. Select the **Traffic Profiles** group.

The Traffic Profile Administration page opens in the work area and lists available traffic profiles.

3. Click **Create Group**.

The Create Group editor page opens.

4. Enter the **Name** of the new traffic profile group.

The name can only contain the characters A–Z, a–z, 0–9, period (.), hyphen (-), and underline (_). The maximum length is 250 characters.

5. (Optional) Enter a **Description / Location** of the traffic profile group.

6. Click **Save**.

The traffic profile group is created.

Adding a Traffic Profile to a Traffic Profile Group

To add a traffic profile to a traffic profile group:

1. From the **Policy Server** section of the navigation pane, select **Traffic Profiles**.
The content tree displays a list of traffic profile group; the initial group is **ALL**.
2. From the content tree, select a Traffic Profile group.
The Traffic Profile Administration page opens in the work area and lists the contents of the selected traffic profile group.
3. Click **Add Traffic Profile**.
The Add Traffic Profile page opens and lists the traffic profiles that are not part of the group.
4. Click on the traffic profile you want to add; use the Ctrl or Shift keys to select multiple traffic profiles.
5. Click **Save**.
The selected traffic profiles are added to the traffic profile group.

Modifying a Traffic Profile Group

To modify a traffic profile group:

1. From the **Policy Server** section of the navigation pane, select **Traffic Profiles**.
The content tree displays a list of traffic profile group; the initial group is **ALL**.
2. From the content tree, select the traffic profile group you want to modify.
The Traffic Profile Administration page opens in the work area.
3. Click **Modify**.
The Modify Group page opens.
4. Edit the **Name** or **Description / Location** fields.
The name can only contain the characters A through Z, a through z, 0 through 9, period (.), hyphen (-), and underline (_). The maximum length is 255 characters.
5. Click **Save**.
The group is modified.

Removing a Traffic Profile from a Traffic Profile Group

Removing a traffic profile from a traffic profile group does not delete the profile. To delete a traffic profile, see [Deleting a Traffic Profile](#).
To remove a traffic profile from a traffic profile group:

1. From the **Policy Server** section of the navigation pane, select **Traffic Profiles**.
The content tree displays a list of traffic profile group; the initial group is **ALL**.
2. From the content tree, select the traffic profile group.
The Traffic Profile Administration page opens in the work area and lists the contents of the traffic profile group.
3. Remove the traffic profile using one of the following methods:
 - Click  (scissors icon) located to the right of the traffic profile you want to remove.

- From the traffic profile group in the content tree, select the traffic profile and click **Remove**.

The traffic profile is removed from the group; there is no confirmation message.

Deleting a Traffic Profile Group

Deleting a traffic profile group does not delete any traffic profiles associated with the deleted group; profiles remain in the **ALL** group. You cannot delete the **ALL** group.

To delete a traffic profile group:

1. From the **Policy Server** section of the navigation pane, select **Traffic Profiles**.

The content tree displays a list of traffic profile group; the initial group is **ALL**.

2. From the content tree, select the traffic profile group.

The Traffic Profile Administration page opens in the work area and lists the contents of the selected traffic profile group.

3. Click **Delete**.

A confirmation message displays.

4. Click **OK** to delete the group.

The traffic profile group is deleted.

Managing Subscriber Keys

This chapter describes how to create and manage subscriber keys in the CMP system.

In a wireless network, a subscriber key associates subscriber IDs with RADIUS messages for RADIUS accounting purposes.

**Note:**

The actual options you see depend on whether or not your CMP system is configured for RADIUS CoA mode.

About Subscriber Keys

**Note:**

Subscriber keys is a function that is applicable to RADIUS mode only. For more information on RADIUS configuration, see *CMP Wireless User's Guide*.

An MPE device must create a data session to track the life cycle of the request and process of any subsequent Interim-Update messages or a RADIUS Accounting-Stop message, when a RADIUS Accounting-Start message is received from:

- An AAA server or from a broadband network gateway (BNG) system
- A RADIUS Interim-Update message is received for an unknown session

To create this session, the MPE device determines a subscriber ID from the RADIUS message using subscriber keys. You configure subscriber keys using the CMP system. Subscriber keys are associated with individual BNG systems.

The subscriber key is a combination of specified type-length values (TLVs) or vendor-specific attributes (VSAs) found in the RADIUS message. The order in which the attribute values are combined is defined in the CMP system. After the subscriber key is computed, the key is matched against the subscribers defined on the MPE device:

- If no match is found, the MPE device initiates an SPR database lookup:
 - If the lookup succeeds, the request is parsed for creating a list of VSAs to be included in a RADIUS Change of Authorization (CoA) message and sent to the BNG system.
 - If the lookup fails and if the RADIUS configuration value **Validate User** is set to **true**, the request is rejected.
- If a match is found, the MPE device creates a dummy user instance to store necessary information for later use.

For more information on CoA messages, see [Managing RADIUS CoA Templates](#).

Creating a Subscriber Key



Note:

Subscriber keys is a function that is applicable to RADIUS CoA mode only.

To create a subscriber key:

1. From the **Policy Server** section of the navigation pane, select **Subscriber Keys**.
The content tree displays the **Subscriber Keys** group.
2. Select the **Subscriber Keys** group.
The Subscriber Keys Administration page opens in the work area.
3. Click **Create Subscriber Key**.
The New Subscriber Key page opens.
4. Enter the **Name** you assign to the subscriber key.
Enter a string.
5. Add a subscriber key.
 - a. Click **Add**. The Add Subscriber Key Field window opens.
TLVs and VSAs are concatenated in the order in which you define them here.
 - b. **Vendor** — Select the available vendor from the list:
 - **IETF** (default)
 - **3GPP**
 - **3GPP2**
 - **Camiant**
 - **Cisco**
 - **Cisco-BBSM**
 - **Cisco-VPN3000**
 - **Cisco-VPN5000**
 - **Juniper**
 - **Juniper-M-Series**
 - Any defined custom vendors are displayed at the end of the list; for more information, see [Managing Custom Vendors](#)
 - c. **TLV/VSA** — Select the TLV or VSA from the list.
The choices are extensive and are not listed here. Any defined custom TLVs or VSAs are displayed at the end of the list; for more information, see [Managing Custom VSAs](#).
 - d. **Delimiter** — Enter the delimiter between fields used by the vendor.
 - e. Click **Save**.

6. (Optional) Add, modify, or delete subscriber keys.
 - Cloning an entry in the table
 - a. Select an entry in the table.
 - b. Click  **Clone**. The Clone window opens with the information for the entry.
 - c. Make changes as required.
 - d. Click **Save**. The entry is added to the table.
 - Editing an entry in the table
 - a. Select the entry in the table.
 - b. Click  **Edit**. The Edit Response window opens, displaying the information for the entry.
 - c. Make changes as required.
 - d. Click **Save**. The entry is updated in the table.
 - Deleting a value from the table
 - a. Select the entry in the table.
 - b. Click  **Delete**. A confirmation message displays.
 - c. Click **Delete** to remove the entry. The entry is removed from the table.
7. Click **Save**.

The subscriber key is displayed in the Subscriber Keys Administration page. After you define subscriber keys, they can be matched against subscribers currently known in the system.

Modifying a Subscriber Key

1. From the **Policy Server** section of the navigation pane, select **Subscriber Keys**.

The Subscriber Keys Administration page opens in the work area, listing the defined subscriber keys.
2. Select the subscriber key you want to modify.

The Subscriber Keys Administration page displays information about the subscriber key.
3. Click **Modify**.

The Modify Subscriber Key page opens.
4. Modify subscriber key information.

For a description of the fields contained on this page, see [Creating a Subscriber Key](#).
5. Click **Save**.

The subscriber key definition is modified.

Deleting a Subscriber Key

1. From the **Policy Server** section of the navigation pane, select **Subscriber Keys**.

The Subscriber Keys Administration page opens in the work area, listing the defined subscriber keys.

2. Delete the subscriber key using one of the following methods:
 - From the work area, click  (trash can icon), located to the right of the subscriber key.
 - From the content tree, select the subscriber key and click **Delete**.

A confirmation message displays.

3. Click **OK**.

The subscriber key is deleted.

Part III

Writing Policy Rules: Conditions, Actions, and Variables Reference

The policy wizard supports a large number of conditions, actions, and variables that can be used for constructing policy rules. This chapter provides a list of all available conditions, actions, and variables.



Note:

Some conditions, actions, and variables may not appear in some modes. The actual conditions, actions, and variables available in the policy wizard depend on the modes in which your CMP system is configured.

Conditions for Writing Policy Rules

The policy wizard supports a large number of conditions that can be used for constructing policy rules. To help you find the conditions you want, the conditions are organized into different categories, which are summarized in [Policy Condition Categories](#).

The conditions that are included within each of these categories are described in the sections that follow. Within each category, conditions are listed in alphabetical order. The parameters that can be modified within each condition are also detailed.

Policy Condition Categories

Application

All Modes

Conditions related to the application associated with the request. See [Application Conditions](#).



Note:

This category is disabled for SPC mode.

Device Usage

All Modes

Conditions related to the calculated usage for the network device for which the policy rule is being evaluated. This usage includes device-level tracking of both bandwidth and flow/session counts. See [Device Usage Conditions](#).

Mobility

Wireless Mode

Conditions that are based on information associated with wireless networks that include mobile subscribers. See [Mobility Conditions](#).

Network Devices

All Modes

Conditions related to the specific network device for which the policy rule is being evaluated. This includes conditions based on the network device type, as well as those that refer to specific unique identifiers for network devices. See [Network Device Conditions](#).

Notification

Wireless Mode

Conditions related to notifications from Sh and Sy data sources. See [Notification Conditions](#).

Policy Context Properties

All Modes

Conditions related to the context in which a policy is evaluated. See [Policy Context Properties Conditions](#).

Policy Counters

Wireless Mode

Conditions related to policy counters stored in online charging systems (OCSs). See [Policy Counters Conditions](#).

Policy SDP Properties

Wireless Mode

Conditions related to SDP properties that are used to check the codec type (offer/answer) for the device (remote/local). See [Policy SDP Properties Conditions](#).

RADIUS

Wireless Mode

Conditions related to RADIUS Change of Authorization (CoA) requests. See [RADIUS Conditions](#).

Request

All Modes

Conditions that are based on information that is explicitly contained within or related to the protocol message (request) that triggered the policy rule execution. See [Request Conditions](#).



Note:

This category is disabled for the SPC mode.

State Variables

Wireless Mode

Conditions related to state variables in wireless networks. See [State Variables Conditions](#).

Time of Day

All Modes

Conditions related to the time at which the policy rules are being executed. See [Time of Day Conditions](#).

User

All Modes

Conditions related to the subscriber, or subscriber account, that is associated with the protocol message that triggered the policy rule execution. This includes subscriber-level and account-level tracking of usage. See [User Conditions](#).

**Note:**

This category is disabled for SPC mode.

Application Conditions

Application conditions are related to the application associated with the request. See [Managing Application Profiles](#) for information on creating and managing application profiles.

where *AMID* is the application manager ID

Mode

Cable

Syntax

where *number* is the application manager ID

Parameters***number***

A 32-bit numeric value that is greater than 0.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy based on the access manager ID in the message.

where *AppType* is the application type

Mode

Cable

Syntax

where *number* is the application type

Parameters***number***

A 16-bit numeric value that is greater than 0.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy based on the application type in the message (this is a sub-field within the AMID).

where the application is latency sensitive

Mode

Cable, Wireless

Syntax

where the application is latency sensitive

Parameters

None

Description

Triggers a policy when the associated application is latency sensitive (can be set in the CMP system when applications are defined).

where the application *is one of specified name*

Mode

Cable, Wireless

Syntax

where the application *operator-binary* one of *app-name*

Parameters***operator-binary***

One of the following:

- **is** (default)
- **is not**

app-name

Names of an application. The application must exist in the CMP database.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy based on the associated application.

where the application will be using *greater than #* and *less than #* bps
specified class of bandwidth

Mode

Wireline

Syntax

where the application will be using *operator-greater bandwidth* and *operator-less bandwidth* bps *class-of-service* bandwidth

Parameters***operator-greater***

One of the following:

- **greater than or equal to**
- **greater than** (default)

bandwidth

A numeric value that specifies bandwidth in bits per second (bps). You can also specify the type to change the rate per second by specifying one of the following:

- **k**—kilobits per second
- **K**—kilobits per second
- **m**—megabits per second
- **M**—megabits per second
- **g**—gigabits per second
- **G**—gigabits per second

operator-less

One of the following:

- **less than or equal to**
- **less than** (default)

class-of-service

One of the following:

- **Standard Definition**
- **High Definition**

Description

Triggers a policy based on the total amount of bandwidth used by the associated application as it relates to a defined range. This can be further qualified by the allocation class of service of the bandwidth. The total represents the amount of bandwidth that is allocated if the current request is approved.

where the application will be using *greater than #* and *less than # downstream* sessions

Mode

Wireline

Syntax

where the application will be using *operator-greater number* and *operator-less number qos-direction* sessions

Parameters

operator-greater

One of the following:

- **greater than or equal to**
- **greater than** (default)

number

A numeric value.

operator-less

One of the following:

- **less than or equal to**
- **less than** (default)

qos-direction

One of the following:

- **upstream** (default)
- **downstream**

Description

Triggers a policy based on the total number of sessions used by the associated application as it relates to a defined range and direction. The total represents the number of sessions that are allocated if the current request is approved.

where the application will be using *greater than #* and *less than # specified class of sessions*

Mode

Wireline

Syntax

where the application will be using *operator-greater number* and *operator-less number class-of-service* sessions

Parameters***operator-greater***

One of the following:

- **greater than or equal to**
- **greater than** (default)

number

A numeric value.

operator-less

One of the following:

- **less than or equal to**
- **less than** (default)

class-of-service

One of the following:

- **Standard Definition**
- **High Definition**

Description

Triggers a policy based on the total number of sessions used by the associated application as it relates to a defined range. The total represents the number of sessions that are allocated if the current request is approved.

where the application will be using *greater than # bps of specified class of bandwidth*

Mode

Wireline

Syntax

where the application will be using *operator-greater bandwidth bps of class-of-service bandwidth*

Parameters

operator-greater

One of the following:

- **greater than or equal to**
- **greater than** (default)

bandwidth

A numeric value that specifies bandwidth in bits per second (bps). You can also specify the type to change the rate per second by specifying one of the following:

- **k**—kilobits per second
- **K**—kilobits per second
- **m**—megabits per second
- **M**—megabits per second
- **g**—gigabits per second
- **G**—gigabits per second

class-of-service

One of the following:

- **Standard Definition**
- **High Definition**

Description

Triggers a policy based on the total amount of bandwidth used by the associated application as it relates to a defined threshold. This can be further qualified by the allocation class of service of the bandwidth. The total represents the amount of bandwidth that is allocated if the current request is approved.

where the application will be using *greater than* # bps *upstream*
reserved bandwidth

Mode

Cable, Wireless

Syntax

where the application will be using *operator-greater bandwidth bps qos-direction qos-status bandwidth*

Parameters

operator-greater

One of the following:

- **greater than or equal to**

- **greater than** (default)

bandwidth

A numeric value that specifies bandwidth in bits per second (bps). You can also specify the type to change the rate per second by specifying one of the following:

- **k**—kilobits per second
- **K**—kilobits per second
- **m**—megabits per second
- **M**—megabits per second
- **g**—gigabits per second
- **G**—gigabits per second

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

qos-direction

One of the following:

- **upstream** (default)
- **downstream**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

qos-status

One of the following:

- **reserved** (default)
- **committed**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy based on the total amount of bandwidth used by the associated application as it relates to a defined threshold. This can be further qualified by both the direction and allocation status of the bandwidth. The total represents the amount of bandwidth that is allocated if the current request is approved.

where the application will be using *greater than # bps upstream reserved* bandwidth

Mode

Wireline

Syntax

where the application will be using *operator-greater bandwidth bps qos-direction qos-status bandwidth*

Parameters***operator-greater***

One of the following:

- **greater than or equal to**
- **greater than** (default)

bandwidth

A numeric value that specifies bandwidth in bits per second (bps). You can also specify the type to change the rate per second by specifying one of the following:

- **k**—kilobits per second
- **K**—kilobits per second
- **m**—megabits per second
- **M**—megabits per second
- **g**—gigabits per second
- **G**—gigabits per second

qos-direction

One of the following:

- **upstream** (default)
- **downstream**

qos-status

One of the following:

- **reserved** (default)
- **committed**

Description

Triggers a policy based on the total amount of bandwidth used by the associated application as it relates to a defined threshold. This can be further qualified by both the direction and allocation status of the bandwidth. The total represents the amount of bandwidth that is allocated if the current request is approved.

where the application will be using *greater than # sessions*

Syntax

where the application will be using *operator-greater number sessions*

Parameters***operator-greater***

One of the following:

- **greater than or equal to**
- **greater than** (default)

number

A numeric value.

Description

Triggers a policy based on the total number of sessions used by the associated application as it relates to a defined threshold. The total represents the number of sessions that are allocated if the current request is approved.

where the application will be using *greater than # specified class of sessions*

Mode

Wireline

Syntax

where the application will be using *operator-greater number class-of-service sessions*

Parameters***operator-greater***

One of the following:

- **greater than or equal to**
- **greater than** (default)

number

A numeric value.

class-of-service

One of the following:

- **Standard Definition**
- **High Definition**

Description

Triggers a policy based on the total number of sessions used by the associated application as it relates to a defined threshold. The total represents the number of sessions that are allocated if the current request is approved.

where the application will be using *greater than # upstream reserved flows*

Mode

Cable, Wireless

Syntax

where the application will be using *operator-greater bandwidth qos-direction qos-status flows*

Parameters**operator-greater**

One of the following:

- **greater than or equal to**
- **greater than** (default)

bandwidth

A numeric value that specifies bandwidth in bits per second (bps). You can also specify the type to change the rate per second by specifying one of the following:

- **k**—kilobits per second
- **K**—kilobits per second
- **m**—megabits per second
- **M**—megabits per second
- **g**—gigabits per second
- **G**—gigabits per second

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

qos-direction

One of the following:

- **upstream** (default)
- **downstream**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

qos-status

One of the following:

- **reserved** (default)
- **committed**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy based on the total number of flows used by the associated application as it relates to a defined threshold. This can be further qualified by both the direction and allocation status of the flows. The total represents the number of flows that is allocated if the current request is approved.

where there is no application associated with the request

Mode

Cable, Wireless

Syntax

where there is no application associated with the request

Parameters

None

Description

Triggers a policy when there is no associated application.

Device Usage Conditions

Device Usage conditions are related to the calculated usage for the network device for which the policy rule is being evaluated. This usage includes device-level tracking of both bandwidth and flow/session counts.

where the device will be handling *greater than #* and *less than #* bps of *specified class of bandwidth*

Mode

Wireline

Syntax

where the device will be handling *operator-greater bandwidth* and *operator-less bandwidth* bps of *class-of-service* bandwidth

Parameters

operator-greater

One of the following:

- **greater than or equal to**
- **greater than** (default)

bandwidth

A numeric value that specifies bandwidth in bits per second (bps). You can also specify the type to change the rate per second by specifying one of the following:

- **k**—kilobits per second
- **K**—kilobits per second
- **m**—megabits per second
- **M**—megabits per second
- **g**—gigabits per second
- **G**—gigabits per second

operator-less

One of the following:

- **less than or equal to**
- **less than** (default)

class-of-service

One or more of the following:

- **Standard Definition**
- **High Definition**

Description

Triggers a policy based on the total amount of bandwidth used by the current device as it relates to a defined range. This can be further qualified by the class of service of the bandwidth. The total represents the bandwidth that is allocated if the current request is approved.

where the device will be handling *greater than #* and *less than #* bps of *specified class of* sessions

Mode

Wireline

Syntax

where the device will be handling *operator-greater number* and *operator-less number* bps of *class-of-service* sessions

Parameters***operator-greater***

One of the following:

- **greater than or equal to**
- **greater than** (default)

number

A numeric value.

operator-less

One of the following:

- **less than or equal to**
- **less than** (default)

class-of-service

One or more of the following:

- **Standard Definition**
- **High Definition**

Description

Triggers a policy based on the total number of sessions used by the device as it relates to a defined range. This can be further qualified by the class of service of the sessions. The total represents the number of sessions that are allocated if the current request is approved.

where the device will be handling *greater than #* and *less than #* percent of *downstream* capacity

Mode

Wireline

Syntax

where the device will be handling *operator-greater bandwidth* and *operator-less bandwidth* percent of *qos-direction* bandwidth

Parameters***operator-greater***

One of the following:

- **greater than or equal to**
- **greater than** (default)

bandwidth

A numeric value that specifies bandwidth in bits per second (bps). You can also specify the type to change the rate per second by specifying one of the following:

- **k**—kilobits per second
- **K**—kilobits per second
- **m**—megabits per second
- **M**—megabits per second
- **g**—gigabits per second
- **G**—gigabits per second

operator-less

One of the following:

- **less than or equal to**
- **less than** (default)

qos-direction

One of the following:

- **upstream** (default)
- **downstream**

Description

Triggers a policy based on the percentage of capacity used by the current device as it relates to a defined range. This can be further qualified by the direction of the bandwidth. The total represents the bandwidth that is allocated if the current request is approved.

where the device will be handling *greater than #* and *less than # specified class of sessions*

Mode

Wireline

Syntax

where the device will be handling *operator-greater number* and *operator-less number class-of-service* sessions

Parameters***operator-greater***

One of the following:

- **greater than or equal to**
- **greater than** (default)

number

A numeric value.

operator-less

One of the following:

- **less than or equal to**
- **less than** (default)

class-of-service

One or more of the following:

- **Standard Definition**
- **High Definition**

Description

Triggers a policy based on the total number of sessions used by the device as it relates to a defined range. This can be further qualified by the class of service of the sessions. The total represents the number of sessions that are allocated if the current request is approved.

where the device will be handling *greater than # bps downstream bandwidth*

Mode

Wireline

Syntax

where the device will be handling *operator-greater bandwidth bps qos-direction bandwidth*

Parameters

operator-greater

One of the following:

- **greater than or equal to**
- **greater than** (default)

bandwidth

A numeric value that specifies bandwidth in bits per second (bps). You can also specify the type to change the rate per second by specifying one of the following:

- **k**—kilobits per second
- **K**—kilobits per second
- **m**—megabits per second
- **M**—megabits per second
- **g**—gigabits per second
- **G**—gigabits per second

qos-direction

One of the following:

- **upstream** (default)
- **downstream**

Description

Triggers a policy based on the total amount of bandwidth used by the current device as it relates to a defined threshold and direction. The total represents the bandwidth that is allocated if the current request is approved.

where the device will be handling *greater than # bps of specified class of bandwidth*

Mode

Wireline

Syntax

where the device will be handling *operator-greater bandwidth bps of class-of-service bandwidth*

Parameters

operator-greater

One of the following:

- **greater than or equal to**
- **greater than** (default)

bandwidth

A numeric value that specifies bandwidth in bits per second (bps). You can also specify the type to change the rate per second by specifying one of the following:

- **k**—kilobits per second
- **K**—kilobits per second
- **m**—megabits per second
- **M**—megabits per second
- **g**—gigabits per second
- **G**—gigabits per second

class-of-service

One or more of the following:

- **Standard Definition**
- **High Definition**

Description

Triggers a policy based on the total amount of bandwidth used by the current device as it relates to a defined threshold. This is further qualified by the class of service of the bandwidth. The total represents the bandwidth that is allocated if the current request is approved.

where the device will be handling *greater than* # bps reserved bandwidth in total for *specified class of* traffic

Mode

Cable

Syntax

where the device will be handling *operator bandwidth* bps *qos-status* bandwidth in total for *class-of-service* traffic

Parameters**operator**

One of the following:

- **greater than or equal to**
- **greater than**
- **less than or equal to**
- **less than**
- **equal to**
- **not equal to**

The default for this condition is **greater than**.

bandwidth

A numeric value that specifies bandwidth in bits per second (bps). You can also specify the type to change the rate per second by specifying one of the following:

- **k**—kilobits per second
- **K**—kilobits per second
- **m**—megabits per second
- **M**—megabits per second
- **g**—gigabits per second
- **G**—gigabits per second

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

qos-status

One of the following:

- **reserved** (default)
- **committed**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

class-of-service

In Wireless Mode, one (or more) of the following:

- **Background**
- **Conversational**
- **Streaming**
- **Interactive**

In Cable Mode, one (or more) of the following:

- **Best Effort**
- **Non Real-time Polling**
- **Real-time Polling**
- **UGS**

- **Background**
- **Conversational**
- **Streaming**
- **Interactive**

In Wireline Mode, one of the following:

- **Standard Definition**
- **High Definition**

One of the following:

- **Standard Definition**
- **High Definition**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy based on the total amount of bandwidth allocated for specific classes of service by the current device as it relates to a defined threshold. This can be further qualified by the allocation status of the bandwidth. The total represents the bandwidth that is allocated if the current request is approved.

where the device will be handling *greater than* # bps upstream reserved bandwidth

Mode

Cable, Wireless

Syntax

where the device will be handling *operator bandwidth* bps *qos-direction* *qos-status* bandwidth

Parameters

operator

One of the following:

- **greater than or equal to**
- **greater than**
- **less than or equal to**

- **less than**
- **equal to**
- **not equal to**

The default for this condition is **greater than**.

bandwidth

A numeric value that specifies bandwidth in bits per second (bps). You can also specify the type to change the rate per second by specifying one of the following:

- **k**—kilobits per second
- **K**—kilobits per second
- **m**—megabits per second
- **M**—megabits per second
- **g**—gigabits per second
- **G**—gigabits per second



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

qos-direction

One of the following:

- **upstream** (default)
- **downstream**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

qos-status

One of the following:

- **reserved** (default)
- **committed**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy based on the total amount of bandwidth used by the current device as it relates to a defined threshold. This can be further qualified by both the direction and allocation status of the bandwidth. The total represents the bandwidth that is allocated if the current request is approved.

where the device will be handling *greater than* # bps *upstream reserved* bandwidth in total for *specified application*

Mode

Cable, Wireless

Syntax

where the device will be handling *operator bandwidth* bps *bandwidth qos-direction* *qos-status* bandwidth in total for *app-name*

Parameters***operator***

One of the following:

- **greater than or equal to**
- **greater than**
- **less than or equal to**
- **less than**
- **equal to**
- **not equal to**

The default for this condition is **greater than**.

bandwidth

A numeric value that specifies bandwidth in bits per second (bps). You can also specify the type to change the rate per second by specifying one of the following:

- **k**—kilobits per second
- **K**—kilobits per second
- **m**—megabits per second
- **M**—megabits per second

- **g**—gigabits per second
- **G**—gigabits per second



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

qos-direction

One of the following:

- **upstream** (default)
- **downstream**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

qos-status

One of the following:

- **reserved** (default)
- **committed**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

app-name

Names of an application. The application must exist in the CMP database.

Description

Triggers a policy based on the total amount of bandwidth allocated for specific applications by the current device as it relates to a defined threshold. This can be further qualified by both the direction and allocation status of the bandwidth. The total represents the bandwidth that is allocated if the current request is approved.

where the device will be handling *greater than # downstream* sessions

Mode

Wireline

Syntax

where the device will be handling *operator-greater number qos_direction* sessions

Parameters***operator-greater***

One of the following:

- **greater than or equal to**
- **greater than** (default)

number

See common parameters.

qos-direction

See common parameters.

Description

Triggers a policy based on the total number of sessions used by the device as it relates to a defined direction and threshold. The total represents the number of sessions that are allocated if the current request is approved.

where the device will be handling *greater than # percent of downstream capacity*

Mode

Wireline

Syntax

where the device will be handling *operator percent percent of qos-direction capacity*

Parameters***operator***

One of the following:

- **greater than or equal to**
- **greater than**
- **less than or equal to**
- **less than**

- **equal to**
- **not equal to**

percent

A numeric value.

qos-direction

One of the following:

- **upstream** (default)
- **downstream**

Description

Triggers a policy based on the percent of bandwidth capacity used by the current device as it relates to a defined threshold. This can be further qualified by the direction of the bandwidth. The total represents the bandwidth that is allocated if the current request is approved.

where the device will be handling *greater than* # percent of *reserved* capacity for *specified class of* traffic

Mode

Cable

Syntax

where the device will be handling *operator* *percent* percent of *qos-status* capacity for *class-of-service* traffic

Parameters

operator

One of the following:

- **greater than or equal to**
- **greater than**
- **less than or equal to**
- **less than**
- **equal to**
- **not equal to**

The default for this condition is **greater than**.

percent

An integer value between 0 and 100.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

qos-status

One of the following:

- **reserved** (default)
- **committed**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

class-of-service

In Wireless Mode, one (or more) of the following:

- **Background**
- **Conversational**
- **Streaming**
- **Interactive**

In Cable Mode, one (or more) of the following:

- **Best Effort**
- **Non Real-time Polling**
- **Real-time Polling**
- **UGS**
- **Background**
- **Conversational**
- **Streaming**
- **Interactive**

In Wireline Mode, one of the following:

- **Standard Definition**
- **High Definition**

One of the following:

- **Standard Definition**

- **High Definition**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy based on the percent of bandwidth capacity allocated for specific classes of service by the current device as it relates to a defined threshold. This can be further qualified by the allocation status of the bandwidth. The total represents the bandwidth that is allocated if the current request is approved.

where the device will be handling *greater than* # percent of *upstream reserved* capacity

Mode

Cable, Wireless

Syntax

where the device will be handling *operator percent percent of qos-direction qos-status capacity*

Parameters***operator***

One of the following:

- **greater than or equal to**
- **greater than**
- **less than or equal to**
- **less than**
- **equal to**
- **not equal to**

The default for this condition is **greater than**.

percent

An integer value between 0 and 100.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

qos-direction

One of the following:

- **upstream** (default)
- **downstream**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

qos-status

One of the following:

- **reserved** (default)
- **committed**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy based on the percent of bandwidth capacity used by the current device as it relates to a defined threshold. This can be further qualified by both the direction and allocation status of the bandwidth. The total represents the bandwidth that is allocated if the current request is approved.

where the device will be handling *greater than* # percent of *upstream reserved* capacity for *specified application*

Mode

Cable, Wireless

Syntax

where the device will be handling *operator percent percent of qos-direction qos-status capacity for app-name*

Parameters

operator

One of the following:

- **greater than or equal to**
- **greater than**
- **less than or equal to**
- **less than**
- **equal to**
- **not equal to**

The default for this condition is **greater than**.

percent

An integer value between 0 and 100.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

qos-direction

One of the following:

- **upstream** (default)
- **downstream**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

qos-status

One of the following:

- **reserved** (default)
- **committed**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

app-name

Names of an application. The application must exist in the CMP database.

Description

Triggers a policy based on the percent of bandwidth capacity allocated for specific applications by the current device as it relates to a defined threshold. This can be further qualified by both the direction and allocation status of the bandwidth. The total represents the bandwidth that is allocated if the current request is approved.

where the device will be handling *greater than* # *reserved* flows in total for *specified class of traffic*

Mode

Cable

Syntax

where the device will be handling *operator number qos-status* flows in total for *class-of-service* traffic

Parameters***operator***

One of the following:

- **greater than or equal to**
- **greater than**
- **less than or equal to**
- **less than**
- **equal to**
- **not equal to**

The default for this condition is **greater than**.

number

A numeric value.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

qos-status

One of the following:

- **reserved** (default)
- **committed**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

class-of-service

In Wireless Mode, one (or more) of the following:

- **Background**
- **Conversational**
- **Streaming**
- **Interactive**

In Cable Mode, one (or more) of the following:

- **Best Effort**
- **Non Real-time Polling**
- **Real-time Polling**
- **UGS**
- **Background**
- **Conversational**
- **Streaming**
- **Interactive**

In Wireline Mode, one of the following:

- **Standard Definition**
- **High Definition**

One of the following:

- **Standard Definition**

- **High Definition**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy based on the total number of flows for specific classes of service used by the current device as it relates to a defined threshold. This can be further qualified by the allocation status of the flows. The total represents the number of flows that are allocated if the current request is approved.

where the device will be handling *greater than # specified class of sessions*

Mode

Wireline

Syntax

where the device will be handling *operator-greater number class-of-service sessions*

Parameters***operator-greater***

One of the following:

- **greater than or equal to**
- **greater than** (default)

number

A numeric value.

class-of-service

One or more of the following:

- **Standard Definition**
- **High Definition**

Description

Triggers a policy based on the total number of sessions used by the device as it relates to a defined threshold. The total represents the number of sessions that are allocated if the current request is approved.

where the device will be handling *greater than* # *upstream reserved* flows

Mode

Cable, Wireless

Syntax

where the device will be handling *operator number qos-direction qos-status* flows

Parameters

operator

One of the following:

- **greater than or equal to**
- **greater than**
- **less than or equal to**
- **less than**
- **equal to**
- **not equal to**

The default for this condition is **greater than**.

number

A numeric value.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

qos-direction

One of the following:

- **upstream** (default)
- **downstream**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

qos-status

One of the following:

- **reserved** (default)
- **committed**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy based on the total number of flows used by the current device as it relates to a defined threshold. This can be further qualified by both the direction and allocation status of the flows. The total represents the number of flows that are allocated if the current request is approved.

where the device will be handling *greater than # upstream reserved* flows in total for *specified application*

Mode

Cable, Wireless

Syntax

where the device will be handling *operator number qos-direction qos-status* flows in total for *app-name*

Parameters**operator**

One of the following:

- **greater than or equal to**
- **greater than**
- **less than or equal to**
- **less than**
- **equal to**
- **not equal to**

The default for this condition is **greater than**.

number

A numeric value.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

qos-direction

One of the following:

- **upstream** (default)
- **downstream**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

qos-status

One of the following:

- **reserved** (default)
- **committed**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

app-name

Names of an application. The application must exist in the CMP database.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy based on the total number of flows for specific applications used by the current device as it relates to a defined threshold. This can be further qualified by

both the direction and allocation status of the flows. The total represents the number of flows that are allocated if the current request is approved.

Mobility Conditions

Mobility conditions are based on information associated with networks that include mobile subscribers (such as a wireless network).

where network initiated requests are *supported*

Mode

Wireless

Syntax

where network initiated requests are *support*

Parameters

support

One of the following:

- **not supported**
- **supported** (default)



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is only evaluated when network initiated requests are or are not supported.

where the APN *matches one of specified APN value(s)*

Mode

Wireless

Syntax

where the APN *matches-op match-list*

Parameters

matches-op

One of the following:

- **matches one of** (default)
- **does not match any of**

match-list

A comma-separated list of values, where each value is a wildcard match pattern that uses the * (asterisk) character to match zero or more characters and the ? (question mark) character to match exactly one character.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is only evaluated for one or more specific access point name (APN) values (based on matching wildcard patterns). A valid APN value is any domain name; for example: `network.operator.com`.

where the BSID *matches one of specified Bsid value(s)*

Mode

Wireless

Syntax

where the BSID *matches-op match-list*

Parameters***matches-op***

One of the following:

- **matches one of** (default)
- **does not match any of**

match-list

A comma-separated list of values, where each value is a wildcard match pattern that uses the * (asterisk) character to match zero or more characters and the ? (question mark) character to match exactly one character.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is only evaluated for one or more specific BSID values (based on matching wildcard patterns).

where the Cell Identifier *matches one of specified CI value(s)*

Mode

Wireless

Syntax

where the Cell Identifier *matches-op match-list*

Parameters***matches-op***

One of the following:

- **matches one of** (default)
- **does not match any of**

match-list

A comma-separated list of values, where each value is a wildcard match pattern that uses the * (asterisk) character to match zero or more characters and the ? (question mark) character to match exactly one character.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is only evaluated for one or more specific Cell Identifier values (based on matching wildcard patterns). A valid Cell Identifier is an integer between 0 and 65535.

where the cell state is *specified*

Mode

Wireless

Syntax

where the cell state is *state*

Parameters**state**

One of the following:

- **congested**
- **not congested**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is evaluated based on the level of congestion in the cell.

where the CSG Access Mode is closed

Mode

Wireless

Syntax

where the CSG Access Mode is *Closed*

Parameter**Closed**

Closed or Hybrid

Description

Triggers a policy value based on the CSG access mode.

where the CSG ID is available

Mode

Wireless

Syntax

Check whether the CSG ID is available *operator-binary*

Parameters***operator-binary***

One of the following:

- **is** (default)
- **is not**

Description

Triggers a policy that is only evaluated for one or more specific Cell Identifier values (based on matching wildcard patterns). A valid Cell Identifier is an integer between 0 and 65535.

where the CSG ID matches one of specified CSG ID values(s)

Mode

Wireless

Syntax

where the CSG ID is *match-list**matches-op*

Parameter***matches-op***

One of the following:

- **matches one of** (default)
- **does not match any of**

match-list

A comma-separated list of values, where each value is a wildcard match pattern that uses the * (asterisk) character to match zero or more characters and the ? (question mark) character to match exactly one character.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

where the E-UTRAN Cell Identifier *matches one of specified ECI value(s)*

Mode

Wireless

Syntax

where the E-UTRAN Cell Identifier *matches-op match-list*

Parameters***matches-op***

One of the following:

- **matches one of** (default)
- **does not match any of**

match-list

A comma-separated list of values, where each value is a wildcard match pattern that uses the * (asterisk) character to match zero or more characters and the ? (question mark) character to match exactly one character.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is only evaluated for one or more specific E-UTRAN Cell Identifier values (based on matching wildcard patterns).

where the IP address of the Serving Gateway *matches one of specified address(es)*

Mode

Wireless

Syntax

where the IP address of the Serving Gateway *matches-op match-list*

Parameters**matches-op**

One of the following:

- **matches one of** (default)
- **does not match any of**

match-list

A comma-separated list of values, where each value is a wildcard match pattern that uses the * (asterisk) character to match zero or more characters and the ? (question mark) character to match exactly one character.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is only evaluated for one or more specific Serving Gateway addresses (based on matching wildcard patterns).

where the IP address of the Serving PCF *matches one of specified address(es)*

Mode

Wireless

Syntax

where the IP address of the Serving PCF *matches-op match-list*

Parameters***matches-op***

One of the following:

- **matches one of** (default)
- **does not match any of**

match-list

A comma-separated list of values, where each value is a wildcard match pattern that uses the * (asterisk) character to match zero or more characters and the ? (question mark) character to match exactly one character.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is only evaluated for one or more specific Serving PCF addresses (based on matching wildcard patterns).

where the IP-CAN type is *specified*

Mode

Wireless

Syntax

where the IP-CAN type is *ip-can-type*

Parameters

ip-can-type

One or more of the following:

- **3GPP GPRS**
- **3GPP EPS**
- **Non_3GPP EPS**
- **3GPP2**
- **WiMAX**
- **DOCSIS**
- **xDSL**
- **FBA**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is only evaluated for a protocol message with a specific IP-CAN type.

where the Location Area Code *matches one of specified LAC value(s)*

Mode

Wireless

Syntax

where the Location Area Code *matches-op match-list*

Parameters

matches-op

One of the following:

- **matches one of** (default)
- **does not match any of**

match-list

A comma-separated list of values, where each value is a wildcard match pattern that uses the * (asterisk) character to match zero or more characters and the ? (question mark) character to match exactly one character.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is only evaluated for one or more specific Location Area Code values (based on matching wildcard patterns). A valid Location Area Code is an integer between 0 and 65535.

where the mobile session *supports* sponsored connectivity

Mode

Wireless

Syntax

where the mobile session *support* sponsored connectivity

Parameters***support***

One of the following:

- **does not support**
- **supports** (default)

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that evaluates whether or not the mobile session supports sponsored data connectivity. This condition supports sponsored data connectivity for both Gx and Rx requests.

Example 35-1 Example

The following condition evaluates as true of the mobile session supports sponsored data connectivity:

where the mobile session *supports* sponsored connectivity

where the MSTimezone DST is *configured daylight savings in hours*

Mode

Wireless

Syntax

where the MSTimezone DST is *offset*

Parameters

offset

One of the following:

- **0 hours**
- **1 hour**
- **2 hours**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is only evaluated if the applied Daylight Saving Time offset for the location of a mobile subscriber/mobile station (MS) matches the parameter.

where the MSTimezone offset is *configured timezone offset*

Mode

Wireless

Syntax

where the MSTimezone offset is *offset*

Parameters

offset

Greenwich Mean Time (GMT) time zone offset.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is only evaluated if the applied time zone for a mobile subscriber/mobile station (MS) matches the parameter.

where the RAT type is *specified*

Mode

Wireless

Syntax

where the RAT type is *rat-type*

Parameters***rat-type***

One or more of the following:

- **GERAN**
- **UTRAN**
- **HSPA Evolution**
- **UMA/GAN**
- **EUTRAN**
- **EUTRAN NB IoT**
- **WLAN**
- **CDMA2000 1x**
- **HRPD**
- **UMB**
- **eHRPD**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is only evaluated for a protocol message with a specific Radio Access Technology (RAT) type.

Example 35-2 Example

The following example changes usage tracking when a user goes into a high rate packet data (HRPD) RAT type:

```
where the RAT type is HRPD  
and where the event trigger is one of RAT CHANGE  
and where the request is modifying an existing session
```

```
grant total volume to 100 percent used for hrpd using key3  
continue processing message
```

where the Routing Area Code *matches one of specified RAC value(s)*

Mode

Wireless

Syntax

```
where the Routing Area Code matches-op match-list
```

Parameters

matches-op

One of the following:

- **matches one of** (default)
- **does not match any of**

match-list

A comma-separated list of values, where each value is a wildcard match pattern that uses the * (asterisk) character to match zero or more characters and the ? (question mark) character to match exactly one character.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is only evaluated for one or more specific RAC values (based on matching wildcard patterns).

where the Routing Area Identifier *matches one of specified RAI value(s)*

Mode

Wireless

Syntax

where the Routing Area Identifier *matches-op match-list*

Parameters***matches-op***

One of the following:

- **matches one of** (default)
- **does not match any of**

match-list

A comma-separated list of values, where each value is a wildcard match pattern that uses the * (asterisk) character to match zero or more characters and the ? (question mark) character to match exactly one character.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is only evaluated for one or more specific Routing Area Identifier values (based on matching wildcard patterns). For a description of the format of a Routing Area Identifier, see the 3GPP TS 23.003 standard.

where the Service Area Code *matches one of specified SAC value(s)*

Mode

Wireless

Syntax

where the Service Area Code *matches-op match-list*

Parameters***matches-op***

One of the following:

- **matches one of** (default)
- **does not match any of**

match-list

A comma-separated list of values, where each value is a wildcard match pattern that uses the * (asterisk) character to match zero or more characters and the ? (question mark) character to match exactly one character.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is only evaluated for one or more specific Service Area Code values (based on matching wildcard patterns). A valid Service Area Code is an integer between 0 and 65535.

where the Serving MCC-MNC *matches one of specified MCC-MNC value(s)*

Mode

Wireless

Syntax

where the Serving MCC-MNC *matches-op match-list*

Parameters**matches-op**

One of the following:

- **matches one of** (default)
- **does not match any of**

match-list

A comma-separated list of values, where each value is a wildcard match pattern that uses the * (asterisk) character to match zero or more characters and the ? (question mark) character to match exactly one character.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is only evaluated for one or more specific mobile country code (MCC)-mobile network code (MNC) values (based on matching wildcard patterns). A valid value consists of a 3-digit mobile country code and a 2- or 3-digit mobile network code, such as 123045. See the *CMP Wireless User's Guide* for information on mapping serving gateways to MCCs and MNCs.

where the subscribed PRA area *matches one of specified PRA area(s)*

Mode

Wireless mode with the 3GPP mode enabled.

Syntax

where the subscribed PRA area *matches-op pra-areas*

Parameters

matches-op

One of the following:

- **matches one of** (default)
- **does not match any of**

pra-areas

A single area or multiple specific PRA areas selected from the defined PRA areas, manually input, or Default.

- **CMP defined PRA lists**
Select one or more defined PRA lists
- **Manual Input**
Enter the identifier for the PRA in hexadecimal format or a custom PRA from a subscriber profile in the format *{User.CustomField}*. For information on creating custom fields in subscriber profiles, see the *CMP Wireless User's Guide*.

The manual input format for multiple PRAs is:

```
PRA
identifier1 [;PRA element list1],PRA identifier2 [; PRA element
list2],...
```

The format of PRA identifier and PRA Element List is according to section 8.108 of TS 29.274[9]. It is specified in Hexadecimal format. If only has a PRA identifier then the PRA area is a predefined PRA area. If both PRA identifier and PRA Element List exists then it is a UE-dedicated PRA Area. The manual input is typically used to input a temporally PRA area. The manual input can also be used to get a PRA area from Custom field of subscriber. For example, *{User.Custom4}*. If the operator wants to manually input a PRA area they need to get the Hexadecimal value for each. Different vendors/operators

should interact or exchange PRA info using the Hexadecimal representation as defined in section 8.108 of TS 29.274[9].

The manual input format for a single PRA is:

```
PRA identifier [, PRA element list]
```

- **Default**

The PRA to which the user equipment is already subscribed, if any.

The Default option specifies using the default PRA area. The default PRA is the PRA area subscribed or provisioned by the PCRF for the UE during IP-CAN session life cycle. It is either a UE- dedicated or predefined PRA area. It can be a PRA area that is retrieved from the subscriber profile (normally UE-dedicated) or a PRA area defined in the CMP (normally predefined). When used, this Default option means to check whether the UE has subscribed to a PRA area but does not care what the PRA area is.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is only evaluated for one or more specific PRA values. If **default area** is selected as the definition for the parameter *pra-areas*, the policy is only evaluated if the user equipment is already subscribed to a PRA.

where the Tracking Area Code *matches one of specified TAC value(s)*

Mode

Wireless

Syntax

where the Tracking Area Code *matches-op match-list*

Parameters

matches-op

One of the following:

- **matches one of** (default)
- **does not match any of**

match-list

A comma-separated list of values, where each value is a wildcard match pattern that uses the * (asterisk) character to match zero or more characters and the ? (question mark) character to match exactly one character.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is only evaluated for one or more specific Tracking Area Code values (based on matching wildcard patterns).

where the UE is *inside/outside/inactive* subscribed PRA area for any one of *specified PRA area(s)*

Mode

Wireless mode with the 3GPP mode enabled.

Syntax

where the UE is *location* subscribed PRA area *PRA areas*

Parameters***location***

One of the following:

- **inside**
- **outside**
- **inactive**

pra-areas

A single area or multiple specific PRA areas selected from the defined PRA areas, manually input, or Default.

- **CMP defined PRA lists**

Select one or more defined PRA lists

- **Manual Input**

Enter the identifier for the PRA in hexadecimal format or a custom PRA from a subscriber profile in the format *{User.CustomField}*. For information on creating custom fields in subscriber profiles, see the *CMP Wireless User's Guide*.

The manual input format for multiple PRAs is:

```
PRA
identifier1 [;PRA element list1],PRA identifier2 [; PRA element
list2],...
```

The format of PRA identifier and PRA Element List is according to section 8.108 of TS 29.274[9]. It is specified in Hexadecimal format. If only has a PRA identifier then the PRA area is a predefined PRA area. If both PRA identifier and PRA Element List exists then it is a UE-dedicated PRA Area. The manual input is typically used to input a temporally PRA area. The manual input can also be used to get a PRA area from Custom field of subscriber. For example, {User.Custom4}. If the operator wants to manually input a PRA area they need to get the Hexadecimal value for each. Different vendors/operators should interact or exchange PRA info using the Hexadecimal representation as defined in section 8.108 of TS 29.274[9].

The manual input format for a single PRA is:

```
PRA identifier [, PRA element list]
```

- **Default**

The PRA to which the user equipment is already subscribed, if any.

The Default option specifies using the default PRA area. The default PRA is the PRA area subscribed or provisioned by the PCRF for the UE during IP-CAN session life cycle. It is either a UE- dedicated or predefined PRA area. It can be a PRA area that is retrieved from the subscriber profile (normally UE-dedicated) or a PRA area defined in the CMP (normally predefined). When used , this Default option means to check whether the UE has subscribed to a PRA area but does not care what the PRA area is.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is only evaluated when the user equipment is or is not inside the subscribed PRA.

where the UE is member of the CSG

Mode

Wireless

Syntax

where the UE is member of CSG *operator-binary*

Parameter

operator-binary

One of the following:

- **is** (default)
- **is not**

Description

Triggers a policy that is evaluated on the basis whether UE is a member of CSG

Network Device Conditions

Network Device conditions are related to the specific network device for which the policy rule is being evaluated. This includes conditions based on the network device type, as well as those that refer to specific unique identifiers for network devices. See the appropriate CMP User's Guide for information on defining the network elements available in your network.

where # is the CMTS blade index

Mode

Cable

Syntax

where *number* is the CMTS blade index

Parameters***number***

A numeric value between 0 and 255.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is only evaluated for a specific CMTS blade (based on the index number of the blade).

where # is the CMTS channel index

Mode

Cable

Syntax

where *number* is the CMTS channel index

Parameters

number

A numeric value between 0 and 255.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is only evaluated for a specific CMTS channel (based on the index number of the channel).

where the An-Gw status is *active*

Mode

Wireless

Syntax

where the An-Gw status is *active*

Parameters

active

An-Gw status is either active or inactive.

Click **OK**.

Click **OK**.

Description

Triggers a policy based on whether the An-Gw status is active or not.

where the cable modem IP address is in *specified subnet*

Mode

Cable

Syntax

where the cable modem IP address is in *subnet*

Parameters***subnet***

- An IPv4 subnet in CIDR notation (for example, 1.2.3.0/24).
- An IPv6 subnet (for example, fc00::1006/64).

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is only evaluated for cable modems whose IP address falls within a specific subnet.

where the cable modem IP address is *specified address*

Mode

Cable

Syntax

where the cable modem IP address is *ip-address*

Parameters***ip-address***

An IPv4 or IPv6 address.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is only evaluated for a specific cable modem (based on its IP address).

where the cable modem MAC address is *specified address*

Mode

Cable

Syntax

where the cable modem MAC address is *mac-address*

Parameters

mac-address

MAC address, in the format *hh:hh:hh:hh:hh:hh*.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is only evaluated for protocol messages that are using the MAC address of the cable modem. To evaluate this condition, the MPE device must be configured with cable modem provisioning information.

where the device name *matches one of specified name(s)*

Mode

Cable, Wireless

Syntax

where the device name *matches-op match-list*

Parameters

matches-op

One of the following:

- **matches one of** (default)
- **does not match any of**

match-list

A comma-separated list of values, where each value is a wildcard match pattern that uses the * (asterisk) character to match zero or more characters and the ? (question mark) character to match exactly one character.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy based on whether the device name matches one or more wildcard match patterns.

where the device type *is specified type*

Mode

Cable, Wireless, Wireline

Syntax

where the device type *operator-binary device-type*

Parameters

operator-binary

One of the following:

- **is** (default)
- **is not**

device-type

In Cable mode, one or more of the following:

- **CMTS**
- **Blade**
- **Channel**
- **Cable Modem**
- **CPE**

In Wireless mode, one or more of the following:

- **PDSN**
- **GGSN**
- **HomeAgent**
- **HSGW**
- **PGW**
- **SGW**
- **DPI**

In Wireline mode, one or more of the following:

- **B-RAS**
- **Router**
- **VOD Server**

- **Interface**
- **Subscriber Group**
- **Wireline Gateway**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy based on the device type for which it is evaluated.

where the endpoint IP address is in *specified subnet*

Mode

Cable, Wireless

Syntax

where the endpoint IP address is in *subnet*

Parameters

subnet

- An IPv4 subnet in CIDR notation (for example, 1.2.3.0/24).
- An IPv6 subnet (for example, fc00::1006/64).



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is only evaluated for endpoints whose IP address falls within a specific subnet.

where the endpoint IP address is *specified address*

Mode

Cable, Wireless

Syntax

where the endpoint IP address is *ip-address*

Parameters***ip-address***

An IPv4 or IPv6 address.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is only evaluated for a specific endpoint (based on its IP address).

where the network element name *matches one of specified name(s)*

Mode

Cable, Wireless, Wireline

Syntax

where the network element name *matches-op value-list*

Parameters***matches-op***

One of the following:

- **matches one of** (default)
- **does not match any of**

value-list

A comma-delimited list of values to compare against.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy based on the name of the network element for which it is being evaluated.

where the network element type *is specified type*

Mode

Cable, Wireless, Wireline

Syntax

where the network element type *operator-binary element-type*

Parameters

operator-binary

One of the following:

- **is** (default)
- **is not**

element-type

In Cable mode, only **CMTS** is available.

In Wireless mode, one or more of the following:

- **GGSN**
- **PDSN**
- **HomeAgent**
- **HSGW**
- **PGW**
- **SGW**
- **DPI**

In Wireline mode, one or more of the following:

- **B-RAS**
- **Router**
- **VOD Server**
- **Subscriber Group**
- **Wireline Gateway**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy based on the type of network element for which it is being evaluated. If the policy is being evaluated for a device that is not a network element but is contained within a network element (such as an interface within a router) then the network element container is used as the basis of comparison.

where the network element's description field is equal to *specified description(s)*

Mode

Wireless, Wireline

Syntax

where the network element's description field is equal to *value*

Parameters***value***

String.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is only evaluated if the Description field of the network element matches the specified string.

where the network element's diameter identity *matches one of specified description(s)*

Mode

Wireless

Syntax

where the network element's diameter identity *matches-op value-list*

Parameters***matches-op***

One of the following:

- **matches one of** (default)
- **does not match any of**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

value-list

A comma-delimited list of values to compare against.

The wildcards * (asterisk) and ? (question mark) are allowed.

Description

Triggers a policy that is evaluated based on the diameter identity of the network element.

where the remote MPE is *unavailable*

Mode

Wireless

Syntax

where the remote MPE is *status*

Parameters

status

One of the following:

- available
- unavailable

Click **OK**.

Description

Checks whether the remote site in a geo-redundant configuration is available or not.

Example 35-3 Example

AND

where the enforcement session is an *IP-CAN session*

where the remote MPE is *unavailable*

set session revalidation time to *18000* seconds

where the request is not using the cable modem IP address

Mode

Cable

Syntax

where the request is not using the cable modem IP address

Parameters

None

Description

Triggers a policy that is only evaluated for protocol messages that are not using the IP address of the cable modem. In order to know this, the MPE device must be configured with cable modem provisioning information.

where the request is using the cable modem IP address

Mode

Cable

Syntax

where the request is using the cable modem IP address

Parameters

None

Description

Triggers a policy that is only evaluated for protocol messages that are not using the IP address of the cable modem. In order to know this, the MPE device must be configured with cable modem provisioning information.

where the User Equipment ESN *matches one of specified ESN value(s)*

Mode

Wireless

Syntax

where the User Equipment ESN *matches-op match-list*

Parameters

matches-op

One of the following:

- **matches one of** (default)
- **does not match any of**

match-list

A comma-separated list of values, where each value is a wildcard match pattern that uses the * (asterisk) character to match zero or more characters and the ? (question mark) character to match exactly one character.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is only evaluated for one or more specific ESN values (based on matching wildcard patterns). A valid ESN value has eight hexadecimal digits, representing the 32 bits of the ESN. For example: A01F3D45.

where the User Equipment IMEISV *matches one of specified IMEISV value(s)*

Mode

Wireless

Syntax

where the User Equipment IMEISV *matches-op match-list*

Parameters**matches-op**

One of the following:

- **matches one of** (default)
- **does not match any of**

match-list

A comma-separated list of values, where each value is a wildcard match pattern that uses the * (asterisk) character to match zero or more characters and the ? (question mark) character to match exactly one character.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is only evaluated for one or more specific IMEISV values (based on matching wildcard patterns). A valid IMEISV value has 16 decimal digits, as defined in the 3GPP TS 23.003 standard.

where the User Equipment MAC *matches one of specified MAC value(s)*

Mode

Wireless

Syntax

where the User Equipment MAC *matches-op match-list*

Parameters

matches-op

One of the following:

- **matches one of** (default)
- **does not match any of**

match-list

A comma-separated list of values, where each value is a wildcard match pattern that uses the * (asterisk) character to match zero or more characters and the ? (question mark) character to match exactly one character.

Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is only evaluated for one or more specific Media Access Control (MAC) values (based on matching wildcard patterns). A MAC address is formatted as six groups of two hexadecimal digits separated by colons (:) or hyphens (-).

where the User Equipment MEID *matches one of specified MEID value(s)*

Mode

Wireless

Syntax

where the User Equipment MEID *matches-op match-list*

Parameters

matches-op

One of the following:

- **matches one of** (default)
- **does not match any of**

match-list

A comma-separated list of values, where each value is a wildcard match pattern that uses the * (asterisk) character to match zero or more characters and the ? (question mark) character to match exactly one character.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is only evaluated for one or more specific MEID values (based on matching wildcard patterns). A valid MEID value has 14 hexadecimal characters; for example: 123456789abcde.

Notification Conditions

Notification conditions are related to notifications from Sh and Sy data sources.

The mandatory action **reject message** is not applicable to policies that contain notification conditions. It does not reject the notification. Instead, use the mandatory action **accept message**.

The following optional actions are applicable to policies that contain notification conditions. Optional actions not listed here are not applicable to work with such policies.



Note:

There is no validation done when other policy actions are added. During policy execution they will have no effect.

- clear alarm with severity *`severity level`*, id *`unique alarm identifier`* and message *`message text`*
- disable forwarding to next hop gateway
- disable VLAN tagging
- enable forwarding to next hop gateway with address *none*
- enable VLAN tagging with Id specified

- evaluate policy group *select policy group*
- evaluate policy *select policy*
- Re-authorize all credit control sessions associated with *select scope*
- Re-authorize all PCEF/TDF sessions associated with *select scope*
- Release all credit control sessions associated with *select scope*
- Release all PCEF/TDF sessions associated with *select scope*
- release the session
- remove all policy context properties
- remove all the *scope* state variables and save *always*
- remove policy context property *name*
- remove the *scope* state variable *name* and save *always*
- send http *POST* notification to *select notification destination* with headers *headers* and content *content*
- send http *POST* notification to url *URL* with headers *headers* and content *content*
- send notification to syslog with *`message text`* and severity *`severity level`*
- send notification to trace log with *`message text`* and severity *`severity level`*
- send SMS *`specified`* to *`default`* destination address, *`default`* TON and *`default`* NPI from *`default`* source address, *`default`* TON and *`default`* NPI on user billing day. Request delivery receipt *`default`*.
- send SMS *`specified`* to *`default`* destination address, *`default`* TON and *`default`* NPI from *`default`* source address, *`default`* TON and *`default`* NPI. Request delivery receipt *`default`*.
- send SMS *`specified`* to user on their Billing Day. Request delivery receipt *`default`*.
- send SMS *`specified`* to user. Request delivery receipt *`default`*.
- send SMTP message with the following text/plain content.
- set alarm with severity *`severity level`*, id *`unique alarm identifier`* and message *`message text`*
- set policy context property name to *value*

where notification from Sh datasource is received for *User Profile*

Mode

Wireless

Syntax

where notification from Sh datasource is received for *object-type*

Parameters

object-type

One or more of the following:

- User Profile
- Pool Profile
- Dynamic quota Profile
- Pool Dynamic quota Profile
- Quota Usage
- User state
- Pool Quota Usage
- Pool State
- Service
- User Session Policy
- User Location

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is only evaluated when notification is received from one of the specified object types in an Sh data source. The mandatory action **reject message** is not applicable to this condition.

**Note:**

This condition generates an RAR/RAA message pair for each notification from each selected object type. Using this condition to generate an action for all object types can significantly impact performance. You should generally process only provisioning changes or quota resets.

Example 35-4 Examples

The following example re-authorizes user sessions for all provisioning change notification and when quota usage is reset to zero:

```
where the user is using equal to 100 percent of total volume for plan1
quota
```

```
And where notification from Sh datasource is received for Quota
Usage
```

```
Or where notification from Sh datasource is received for User
Profile, Pool Profile, Dynamic quota Profile, Pool Dynamic quota Profile
re-authorize all PCEF/TDF sessions associated with User
continue processing message
```

If an MPE device is configured to process all notifications (see the *CMP Wireless User's Guide*), but you want to use the functions of a previous releases, you must write a policy rule similar to the following:

```
where notification from Sh datasource is received for User Profile,Pool
Profile,Dynamic quota Profile,Pool Dynamic quota Profile
re-authorize all PCEF/TDF sessions associated with User
continue processing message
```

The following example issues an updated RADIUS CoA message when a Profile Notification Request (PNR) message is received from an SPR system:

```
where notification from Sh datasource is received for Quota Usage
send CoA with CoA10-24
continue processing message
```

Policy Context Properties Conditions

Policy context properties are user-defined name/value string pairs that can be created from policy actions and evaluated from policy conditions. By using policy context properties, one policy can influence the execution of other policies. Policy context properties exist across multiple policy executions on the same request, but are not persistent across requests. Subscriber properties are stored in an SPR system and can be accessed from the SPR multiple times if needed. Subscriber properties exist for multiple requests.

where the policy context property *name exists*

Mode

Cable, Wireless, Wireline

Syntax

where the policy context property *property-name accessibility*

Parameters

property-name

String.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

accessibility

One of the following:

- **exists** (default)
- **does not exist**

Description

Triggers a policy based on whether or not the specified policy context property exists.

where the policy context property *name* is numerically *equal to value*

Mode

Cable, Wireless, Wireline

Syntax

where the policy context property *property-name* is numerically *operator value*

Parameters

property-name

String.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

operator

One of the following:

- **greater than or equal to**
- **greater than**
- **less than or equal to**
- **less than**
- **equal to**
- **not equal to**

For this condition the default is **equal to**.

value

String.

Integer value in the inclusive range of -9,223,372,036,854,775,808 to 9,223,372,036,854,775,807 (that is, -2^{63} to $2^{63}-1$).

Description

Triggers a policy based on a numerical comparison between the specified policy context property value and a specified value.

Example 35-5 Example

The following policy will release the session if the DATA_LIM for the subscriber is changed from non-zero to zero:

```
where the reauth is triggered by subscriber profile update with notification
type SUBSCRIBER_POOL
And where at least one of pool fields DATA_LIM have been updated
And where the policy context property {Previous.Pool.DATA_LIM} is
numerically greater than 0
release the session
accept message
```

where the policy context property *name matches one of `value(s)`*

Mode

Cable, Wireless, Wireline

Syntax

where the policy context property *property-name matches-op `match-list`*

Parameters

property-name

String.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

matches-op

One of the following:

- **matches one of** (default)
- **does not match any of**

match-list

A comma-separated list of values, where each value is a wildcard match pattern that uses the * (asterisk) character to match zero or more characters and the ? (question mark) character to match exactly one character.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy based on whether the specified policy context property value matches a list of specified values (based on matching wildcard patterns).

Policy Method Conditions

Policy Method conditions are related to the methods used to process the policy.

where evaluate the customized method *specified name(s)*

Mode

Wireless

Syntax

where evaluate the customized method *specified name(s)*

Parameters

specified name(s)

The name of one or more policy methods.

Description

Uses customized policy methods to evaluate policies.

Policy Counters Conditions

Policy Counter conditions are related to policy counters stored in online charging servers (OCSs).

where a *current* status exists for Policy Counter IDs *select names*

Mode

Wireless

Syntax

where a *status* status *accessibility* for Policy Counter IDs *counter -name*

Parameters**status**

One of the following:

- **pending**—Accesses the pending status closest to the current time.
- **current**—Accesses the current status (default).

accessibility

One of the following:

- **exists** (default)
- **does not exist**

counter -name

- Select **Policy Counter Id** to select one or more policy counter ID defined in the CMP database.
- Select **Policy Counter ID(s)(CSV)** to enter a comma-separated string of policy counter IDs.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy based on whether the specified policy counter ID property exists or does not exist in the selected counter ID status. See [Managing Policy Counter Identifiers](#) for information on policy counter IDs.

where the Filter-Ids for Policy Counter ID *select name current* status match one or more of *Filter-Ids to match*

Mode

Wireless

Syntax

where the Filter-Ids for Policy Counter ID *counter -name status* status match one or more of *match-list*

Parameters

counter -name

- Select **Policy Counter Id** to select only one policy counter ID defined in the CMP database.
- Select **Policy Counter ID(s)(CSV)** to enter a policy counter IDs.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

status

One of the following:

- **pending**—Accesses the pending status closest to the current time.
- **current**—Accesses the current status (default).

match-list

A comma-separated list of values, where each value is a wildcard match pattern that uses the * (asterisk) character to match zero or more characters and the ? (question mark) character to match exactly one character.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy based on whether the specified policy counter ID property matches the selected counter ID status and filter expression(s). See [Managing Policy Counter Identifiers](#) for information on policy counter IDs.

where the Final-Unit-Action for Policy Counter IDs *select names*
current status matches *Final-Unit-Action to match*

Mode

Wireless

Syntax

where the Final-Unit-Action for Policy Counter IDs *counter -name status*
status matches *action*

Parameters

counter -name

- Select **Policy Counter Id** to select one or more policy counter ID defined in the CMP database.
- Select **Policy Counter ID(s)(CSV)** to enter a comma-separated string of policy counter IDs.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

status

One of the following:

- **pending**—Accesses the pending status closest to the current time.
- **current**—Accesses the current status (default).

action

The action to match. One of the following:

- **ACTION_TERMINATE** (default)
- **ACTION_REDIRECT**
- **ACTION_RESTRICT_ACCESS**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Tests whether the Policy Counter ID contains a Final Unit Action (FUA) attribute-value pair (AVP) matching the specified FUA. See [Managing Policy Counter Identifiers](#) for information on policy counter IDs.

where the Final-Unit-Indication AVP for Policy Counter IDs *select names current status exists*

Mode

Wireless

Syntax

where the Final-Unit-Indication AVP for Policy Counter IDs *counter -name status status accessibility*

Parameters

counter -name

- Select **Policy Counter Id** to select one or more policy counter ID defined in the CMP database.
- Select **Policy Counter ID(s)(CSV)** to enter a comma-separated string of policy counter IDs.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

status

One of the following:

- **pending**—Accesses the pending status closest to the current time.
- **current**—Accesses the current status (default).

accessibility

One of the following:

- **exists** (default)
- **does not exist**

Description

Determines whether the Final-Unit-Indication AVP for the Policy Counter ID is accessible. See [Managing Policy Counter Identifiers](#) for information on policy counter IDs.

where the Policy Counter ID *select name current* status is between *value* and *value*

Mode

Wireless

Syntax

where the policy counter ID *counter -name statusstatus operator-binary*
between *value* and *value*

Parameters

counter -name

- Select **Policy Counter Id** to select only one policy counter ID defined in the CMP database.
- Select **Policy Counter ID(s)(CSV)** to enter a policy counter IDs.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

status

One of the following:

- **pending**—Accesses the pending status closest to the current time.
- **current**—Accesses the current status (default).

operator-binary

One of the following:

- **is** (default)
- **is not**

value

Integer value in the inclusive range of -9,223,372,036,854,775,808 to 9,223,372,036,854,775,807 (that is, -2^{63} to $2^{63}-1$).



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy based on a numerical comparison between the specified policy counter ID value and a pair of specified values, and whether the ID is or is not within the range defined by the two values. See [Managing Policy Counter Identifiers](#) for information on policy counter IDs.

where the Policy Counter ID *select name current* status is contained in Match Lists *select lists*

Mode

Wireless

Syntax

where the Policy Counter ID *counter -name status status operator-binary* contained in Match Lists *match-list*

Parameters

counter -name

- Select **Policy Counter Id** to select only one policy counter ID defined in the CMP database.
- Select **Policy Counter ID(s)(CSV)** to enter a policy counter IDs.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

status

One of the following:

- **pending**—Accesses the pending status closest to the current time.
- **current**—Accesses the current status (default).

operator-binary

One of the following:

- **is** (default)
- **is not**

match-list

A comma-separated list of values, where each value is a wildcard match pattern that uses the * (asterisk) character to match zero or more characters and the ? (question mark) character to match exactly one character.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Selects protocol messages based on whether the status of a policy counter ID matches, or does not match, any of the values in a match list. Any of the types can be selected in combination. The order will match the list from top to bottom. See [Managing Policy Counter Identifiers](#) for information on policy counter IDs. See [Managing Match Lists](#) for information about defining match lists.

where the Policy Counter ID *select name current* status is numerically *equal to value*

Mode

Wireless

Syntax

where the policy context property *counter -name status* status is numerically *operator value*

Parameters

counter -name

- Select **Policy Counter Id** to select one or more policy counter ID defined in the CMP database.
- Select **Policy Counter ID(s)(CSV)** to enter a comma-separated string of policy counter IDs.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

status

One of the following:

- **pending**—Accesses the pending status closest to the current time.
- **current**—Accesses the current status (default).

operator

One of the following:

- **greater than or equal to**
- **greater than**
- **less than or equal to**

- **less than**
- **equal to**
- **not equal to**

For this condition the default is **equal to**.

value

String.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy based on a numerical comparison between the specified policy counter ID status value and a specified value. See [Managing Policy Counter Identifiers](#) for information on policy counter IDs.

where the Policy Counter ID *select name current status matches one of specified value(s)*

Mode

Wireless

Syntax

where the Policy Counter ID *counter -name status status matches-op value-list*

Parameters

counter -name

- Select **Policy Counter Id** to select only one policy counter ID defined in the CMP database.
- Select **Policy Counter ID(s)(CSV)** to enter a policy counter IDs.

status

One of the following:

- **pending**—Accesses the pending status closest to the current time.
- **current**—Accesses the current status (default).

matches-op

One of the following:

- **matches one of** (default)
- **does not match any of**

value-list

A comma-delimited list of values to compare against.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy based on whether the status of a specified policy counter ID value matches, or does not match, a list of specified values (based on matching wildcard patterns). See [Managing Policy Counter Identifiers](#) for information on policy counter IDs.

where the Policy Counter ID *select name* status *is* equal to default status

Mode

Wireless

Syntax

where the Policy Counter ID *counter -name* status *operator-binary* equal to default status

Parameters**counter -name**

- Select **Policy Counter Id** to select only one policy counter ID defined in the CMP database.
- Select **Policy Counter ID(s)(CSV)** to enter a policy counter IDs.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

operator-binary

One of the following:

- **is** (default)
- **is not**

Description

Selects protocol messages based on whether the policy counter ID status is, or is not, equal to the default status defined for the policy counter ID. See [Managing Policy Counter Identifiers](#) for information on policy counter IDs.

where the Policy Counter IDs *select names exists*

Mode

Wireless

Syntax

where the Policy Counter IDs *counter -name accessibility*

Parameters***counter -name***

- Select **Policy Counter Id** to select one or more policy counter ID defined in the CMP database.
- Select **Policy Counter ID(s)(CSV)** to enter a comma-separated string of policy counter IDs.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

accessibility

One of the following:

- **exists** (default)
- **does not exist**

Description

Triggers a policy based on whether or not the specified policy counter ID property exists or does not exist. See [Managing Policy Counter Identifiers](#) for information on policy counter IDs.

where the Sy Session *exists*

Mode

Wireless

Syntax

where the Sy Session *accessibility*

Parameters***accessibility***

One of the following:

- **exists** (default)
- **does not exist**

Description

Determines whether the Sy Session is accessible. See [Managing Policy Counter Identifiers](#) for information on policy counter IDs.

Policy SDP Properties Conditions

Session Description Protocol (SDP) properties conditions identify any specific SDP attributes and evaluate their value. This includes setting proper bandwidth values on related PCC rules. The following conditions are available.

where the *local* codec data is an *offer*

Mode

Wireless

Syntax

where the *sdp_capabilities* codec data is an *codec-type*

Parameters***sdp_capabilities***

Specifies where to search for the SDP property:

- **Local**—The capabilities of the device for the subscriber.
- **Remote**—The capabilities of the device for the remote party.
- **Common**—The capabilities that the local and remote devices have in common.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

codec-type

Specifies the Codec type. The options are:

- **offer** (default)
- **answer**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Checks the Codec type (offer or answer) for a subscribers device (remote, local or both).

where the *local specified SDP property exists*

Mode

Wireless

Syntax

where the *sdp_capabilities SDP property accessibility*

Parameters***sdp_capabilities***

Specifies where to search for the SDP property:

- **Local**—The capabilities of the device for the subscriber.
- **Remote**—The capabilities of the device for the remote party.
- **Common**—The capabilities that the local and remote devices have in common.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

SDP property

A comma-delimited list of SDP properties. Specify the SDP properties using one of the following methods:

- Generic descriptor

sdp.[option]

Where:

option

Is any name (for example, i) or any keyword (for example, a=ptime)

Examples using an SDP generic descriptor:

- where the common `sdp.[a]` exists
- where the remote `sdp.[a=ptime]` exists
- where the common `sdp.[gd]` exists

- **Media descriptor**

`sdp.[m.option]`

Where:

option

- `fmt`
- `port`
- `numberofports`
- `media`
- `proto`

Examples using an SDP media descriptor:

- where the local `sdp.[m]` exists

- **rtpmap**

`sdp.[codec-name(codec-name).rtpmap.OPTION]`

Where:

codec-name

Specifies a codec name.

option

- `payloadtype`
- `clockrate`
- `encodingparameters`

Examples using rtpmap:

- where the remote `sdp.[ codec-name(AMR-WB).rtpmap]` exists

- **fntp**

`sdp.[codec-name(codec-name).fntp.OPTIONS]`

Where:

codec-name

Specifies a codec name.

option

- `fmt`
- `profile-level-id`

- mode-set
- packetization-mode
- Any other parameter to be conveyed

Examples using fmp:

- where the common `sdp.[codec-name(AMR-WB).fmp.fmt]` exists



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

accessibility

One of the following:

- **exists** (default)
- **does not exist**

Description

Checks for the existence or non-existence of any SDP property.

where the *local specified SDP property* is numerically equal to value

Mode

Wireless

Syntax

where the `sdp_capabilities sdp_capabilities` is numerically operator value

Parameters

sdp_capabilities

Specifies where to search for the SDP property:

- **Local**—The capabilities of the device for the subscriber.
- **Remote**—The capabilities of the device for the remote party.
- **Common**—The capabilities that the local and remote devices have in common.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

SDP property

A comma-delimited list of SDP properties. Specify the SDP properties using one of the following methods:

- **Generic descriptor**

Syntax: `sdp.[option]`

Where:

option

Is any name (for example, i) or any keyword (for example, a=ptime)

Examples using an SDP generic descriptor:

- where the common `sdp.[a=ptime]` is numerically equal to 20
- where the common `sdp.[f=hello]` is numerically equal to 20

- **Media descriptor**

Syntax: `sdp.[m.option]`

Where:

option

- `fmt`
- `port`
- `numberofports`
- `media`
- `proto`

Example using an SDP media descriptor:

- where the local `sdp.[m.numberofports]` is numerically equal to 2

- **rtpmap**

Syntax: `sdp.[codec-name(codec-name).rtpmap.OPTION]`

Where:

codec-name

Specifies a codec name.

option

- `payloadtype`
- `clockrate`
- `encodingparameters`

Examples using rtpmap:

- where the local `sdp.[codec-name(AMR-WB).rtpmap.clockrate]` is numerically less than or equal to 16000

- **fmt**

Syntax: `sdp.[codec-name(codec-name).fmt.OPTIONS]`

Where:

codec-name

Specifies a codec name.

option

- `fmt`
- `profile-level-id`
- `mode-set`
- `packetization-mode`
- Any other parameter to be conveyed

Example using `fmt`:

- where the local `sdp.[codec-name(AMR-WB).fmt.mode-set]` is numerically less than or equal to 4



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

operator

One of the following:

- **greater than or equal to**
- **greater than**
- **less than or equal to**
- **less than**
- **equal to**
- **not equal to**

For this condition the default is **equal to**.

value

String.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Compares a numerical SDP property value against a specified number.

where the *local specified SDP property matches one of value(s)*

Mode

Wireless

Syntax

where the *sdp_capabilities SDP property matches-op value-list*

Parameters***sdp_capabilities***

Specifies where to search for the SDP property:

- **Local**—The capabilities of the device for the subscriber.
- **Remote**—The capabilities of the device for the remote party.
- **Common**—The capabilities that the local and remote devices have in common.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

SDP property

A comma-delimited list of SDP properties. Specify the SDP properties using one of the following methods:

- **Generic descriptor**

Syntax: *sdp.[option]*

Where:

option

Is any name (for example, i) or any keyword (for example, a=ptime)

Examples using an SDP generic descriptor:

- where the local *sdp.[i]* matches one of **recvonly**
- where the common *sdp.[a=ptime]* matches one of 20
- where the common *sdp.[a]* matches one of *ptime: 20*
- where the common *sdp.[u]* matches one of *http://www.oracle.com:8080/hr/one.htm*

- where the common `sdp.[u=http://www.oracle.com]` matches one of `8080/hr/one.htm`
- where the common `sdp.[u=http]` matches one of `//www.oracle.com:8080/hr/one.htm`
- where the remote `sdp.[xy]` matches one of `z`
- where the remote `sdp.[xy=z]` matches one of `80`

- **Media descriptor**

Syntax: `sdp.[m.option]`

Where:

option

- `fmt`
- `port`
- `numberofports`
- `media`
- `proto`

Examples using an SDP media descriptor:

- where the common `sdp.[m.fmt]` matches one of `102`
- where the common `sdp.[m.port]` does not match any of `41000,41002`
- where the remote `sdp.[m.media]` matches one of `audio,video`
- where the local `sdp.[m.proto]` matches one of `RTP/AVP`

- **rtpmap**

Syntax: `sdp.[codec-name(codec-name).rtpmap.OPTION]`

Where:

codec-name

Specifies a codec name.

option

- `payloadtype`
- `clockrate`
- `encodingparameters`

Examples using rtpmap:

- where the common `sdp.[ codec-name(AMR-WB).rtpmap]` matches one of `104 AMR-WB/160000`
- where the common `sdp.[ codec-name(AMR-WB).rtpmap.encodingparameters]` matches one of `2`

- where the common `sdp.[ codec-name(AMR-WB).rtpmap.payloadtype]` matches one of 104,102

- **fntp**

Syntax: `sdp.[codec-name(codec-name).fntp.OPTIONS]`

Where:

codec-name

Specifies a codec name.

option

- `fmt`
- `profile-level-id`
- `mode-set`
- `packetization-mode`
- Any other parameter to be conveyed

Examples using fntp:

- where the common `sdp.[codec-name(AMR-WB).fntp.fmt]` matches one of 104,102
- where the common `sdp.[codec-name(AMR-WB).fntp.mode-set]` matches one of 2,4
- where the common `sdp.[codec-name(H264).fntp.profile-level-id]` matches one of 42e00c



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

matches-op

One of the following:

- **matches one of** (default)
- **does not match any of**

value-list

A comma-delimited list of values to compare against.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Checks the Codec type (offer or answer) for a subscribers device (remote, local or both) for specific values.

RADIUS Conditions

RADIUS conditions are related to RADIUS Change of Authorization (CoA) requests.

where the BNG COA destination port *is port number*

Mode

Wireless

Syntax

where the BNG COA destination port *operator-binary port*

Parameters

operator-binary

One of the following:

- **is** (default)
- **is not**

port

Enter a port number.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is evaluated depending on the value of the destination port number of a broadband network gateway associated with the request.

where the RADIUS accounting request is *RADIUS Accounting-Start*

Mode

Wireless

Syntax

where the RADIUS accounting request is *radius-request*

Parameters***radius-request***

One or more of the following:

- **Accounting-Start** (default) — RADIUS Accounting-Start message
- **Accounting-Stop** — RADIUS Accounting-Stop message
- **Interim-Update** — RADIUS Interim-Update message
- **Accounting-On** — RADIUS Accounting-On message
- **Accounting-Off** — RADIUS Accounting-Off message

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Evaluated as true when the RADIUS message has a code field value that matches one of the specified message types.

An Accounting-Start message is interpreted as a request to begin a session; an Accounting-Stop message is interpreted as a request to end a session. An Interim-Update message is interpreted as a keep-alive message. An Accounting-On message is interpreted as meaning the BNG device has restarted, while an Accounting-Off message is interpreted as meaning the BNG device is about to restart; in both cases the MPE device removes all the sessions' state information and any previously installed services, and marks the sessions as stale, to be removed during the next session cleanup cycle.

Example 35-6 Example

```
where the RADIUS accounting request is Accounting-Start
send CoA with CoA Template
```

where the RADIUS request *contains* a TLV / VSA of *name* or *ID*

Mode

Wireless

Syntax

where the RADIUS request *containment* a TLV / VSA of *vsa*

Parameters***containment***

One of the following:

- **contains one of** (default)
- **does not contain any of**

vsa

A VSA or TLV name, in the format *name:vendor_id* or *code*.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Evaluates whether the RADIUS request message contains, or does not contain, the specified vendor-specific attribute (VSA) or type-length-value (TLV). You can specify either a standard TLV or VSA or a custom TLV or VSA number defined in the RADIUS dictionary.

where the RADIUS request contains TLV / VSA *name or ID* whose value *is* contained in Match List *List of TLV / VSA value as string*

Mode

Wireless

Syntax

where the RADIUS request contains TLV / VSA *vsa* whose value *operator-binary* contained in Match List *match-list*

Parameters**vsa**

A TLV or VSA name, in the format *name:vendor_id* or *code*.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

operator-binary

One of the following:

- **is** (default)
- **is not**

match-list

A comma-separated list of values, where each value is a wildcard match pattern that uses the * (asterisk) character to match zero or more characters and the ? (question mark) character to match exactly one character.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Evaluates whether the specified type-length-value (TLV) or vendor-specific attribute (VSA) in a RADIUS request message is contained, or is not contained, in a match list of values. The values are compared as strings. You can specify either a standard TLV or VSA or a custom TLV or VSA number defined in the RADIUS dictionary.

where the RADIUS request contains TLV / VSA *name or ID* whose value is numerically *equal to number*

Mode

Wireless

Syntax

where the RADIUS request contains TLV / VSA *vsa* whose value is numerically *operator number*

Parameters**vsa**

A TLV or VSA name, in the format *name:vendor_id* or *code*.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

operator

One of the following:

- **greater than or equal to**
- **greater than**

- **less than or equal to**
- **less than**
- **equal to**
- **not equal to**

For this condition the default is **equal to**.

number

A numeric value.

 Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Compares the specified type-length-value (TLV) or vendor-specific attribute (VSA) in a RADIUS request message with a numeric value. The values are compared as numbers. You can specify either a standard TLV or VSA or a custom TLV or VSA number defined in the RADIUS dictionary.

where the RADIUS request contains TLV / VSA *name or ID* whose value *matches one of TLV / VSA value as string*

Mode

Wireless

Syntax

where the RADIUS request contains TLV / VSA *vsa* whose value *matches-op value-list*

Parameters

vsa

A TLV or VSA name, in the format *name:vendor_id* or *code*.

 Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

matches-op

One of the following:

- **matches one of** (default)
- **does not match any of**

value-list

A comma-delimited list of values to compare against.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Evaluates whether the RADIUS request message contains, or does not contain, the specified type-length-value (TLV) or vendor-specific attribute (VSA) by comparing the name or ID against a list of values. The values are compared as strings. You can specify either a standard TLV or VSA or a custom TLV or VSA number defined in the RADIUS dictionary.

where the RADIUS request contains VSAs from *vendor*

Mode

Wireless

Syntax

where the RADIUS request contains VSAs from *vendor-list*

Parameters***vendor-list***

One of the following:

- **IETF**
- **3GPP**
- **3GPP2**
- **Camiant**
- **Cisco**
- **Cisco-BBSM**
- **Cisco-VPN3000**
- **Cisco-VPN5000**
- **Juniper**
- **Juniper-M-Series**

- Any defined custom vendors appear at the end of the list; for more information see [Managing Custom Vendors](#)

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Evaluates as true if the RADIUS request message contains a type-length-value (TLV) or vendor-specific attribute (VSA) from the specified vendor. The vendor value can be either a standard or custom value defined in the RADIUS dictionary.

**Note:**

The base RADIUS TLVs are considered as being from IETF.

Request Conditions

Request conditions are based on information that is explicitly contained within, or related to, the protocol message (request) that triggered the policy rule execution.

where at least one Filter-ID AVP exists

Mode

Wireless

Syntax

where at least one Filter-ID AVP exists

Parameters

None

Description

Tests whether the current request contains one or more Filter-ID AVPs.

where at least one Final-Unit-Action matches *Final-Unit-Action to match*

Mode

Wireless

Syntax

where at least one Final-Unit-Action matches *action*

Parameters***action***

One of the following:

- **ACTION_TERMINATE** (default)
- **ACTION_REDIRECT**
- **ACTION_RESTRICT_ACCESS**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Tests whether the current request contains a Final Unit Action (FUA) attribute-value pair (AVP) matching the specified FUA.

where at least one Final-Unit-Indication AVP exists

Mode

Wireless

Syntax

where at least one Final-Unit-Indication AVP exists

Description

Tests whether the current request contains one or more Final-Unit-Indication (FUI) AVPs.

where at least one flow has media type that matches *specified type(s)*

Mode

Wireless

Syntax

where at least one flow has media type that matches *media-type*

Parameters

media-type

One or more of the following, used to determine the type of media:

- **Audio**
- **Video**
- **Data**
- **Application**
- **Control**
- **Text**
- **Message**
- **Other**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy based on whether at least one flow matches one or more of the specified media types.

Example 35-7 Example

where at least one flow has media type that matches *Video,Application*

where at least one flow with media type *specified type(s)* has one of the statuses *specified status(s)*

Mode

Wireless

Syntax

where at least one flow with media type *media-type* has one of the statuses *media-status*

Parameters

media-type

One or more of the following, used to determine the type of media:

- **Audio**
- **Video**
- **Data**
- **Application**
- **Control**
- **Text**
- **Message**
- **Other**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

media-status

One or more of the following status type:

- **Enabled**
- **Enabled Uplink**
- **Enabled Downlink**
- **Disabled**
- **Removed**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy based on whether at least one flow with one of the specified media types matches at least one of the specified statuses.

Example 35-8 Example

where at least one flow with media type *Video* has one of the statuses
Enabled, Enabled Downlink

where Filter-ID AVP does not exist

Mode

Wireless

Syntax

where Filter-ID AVP does not exist

Parameters

None

Description

Tests whether the current request contains no Filter-ID AVPs.

where Final-Unit-Indication AVP does not exist

Mode

Wireless

Syntax

where Final-Unit-Indication AVP does not exist

Parameters

None

Description

Allows for a condition that will determine if the current request contains a Final-Unit-Indication (FUI) AVP.

where the AF-Application-ID is available

Mode

Wireless

Syntax

where the AF-Application-ID *operator-binary* available

Parameters

operator-binary

One of the following:

- **is** (default)
- **is not**

Description

Checks for the presence or absence of the AF Application Identifier field. A valid AF Application identifier is any string describing the application, for example VoIP or streaming.

where the AF-Application-ID matches one of *specified value(s)*

Mode

Cable, Wireless

Syntax

where the AF-Application-ID matches one of *value-list*

Parameters***value-list***

A comma-delimited list of values to compare against.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Selects protocol messages based on the Diameter AF Application Identifier field. A valid AF Application identifier is any string describing the application, for example VoIP or streaming.

Example 35-9 Example

```
where the AF-Application-ID matches one of ptt-application-id
apply PTT to all flows in the request
continue processing message
```

where the Application-Service-Provider-Identity matches one of *specified Application Service Provider Identity(s)*

Mode

Wireless

Syntax

where the Application-Service-Provider-Identity matches one of *value-list*

Parameters

value-list

A comma-delimited list of values to compare against.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Selects protocol messages based on whether the Application-Services-Provider-Identity AVP matches a list of application services providers. This condition supports sponsored data connectivity.

Example 35-10 Example

The following condition is true if the Application-Services-Provider-Identity AVP matches either YouTube or FaceBook.

where the Application-Service-Provider-Identity matches one of
YouTube, FaceBook

where the bearer usage is *General*

Mode

Wireless

Syntax

where the bearer usage is *bearer-usage*

Parameters

bearer-usage

One of the following:

- **General** (default)
- **IMS Signaling**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Selects protocol message based on the user or equipment information.

where the Classifier parameters are equal to *specified value*

Mode

Cable

Syntax

where the Classifier parameters are equal to *classifier*

Parameters***classifier***

One or more of the following:

- **PCMM Classifier (Extended)-Action**
- **PCMM Classifier (Extended)-Activation State**
- **PCMM Classifier (Extended)-Classifier Id**
- **PCMM Classifier (Extended)-Destination Mask**
- **PCMM Classifier (Extended)-Destination Port End**
- **PCMM Classifier (Extended)-Source Mask**
- **PCMM Classifier (Extended)-Source Port End**
- **PCMM Classifier (IPv6)-Destination Address**
- **PCMM Classifier (IPv6)-Destination Prefix Length**
- **PCMM Classifier (IPv6)-Flags**
- **PCMM Classifier (IPv6)-Flow Label**
- **PCMM Classifier (IPv6)-Next Header Type**
- **PCMM Classifier (IPv6)-Source Address**
- **PCMM Classifier (IPv6)-Source Prefix Length**
- **PCMM Classifier (IPv6)-tc-high**
- **PCMM Classifier (IPv6)-tc-low**
- **PCMM Classifier (IPv6)-tc-mask**
- **PCMM Classifier-Destination Address**
- **PCMM Classifier-Destination Port**
- **PCMM Classifier-DSCP/TOS Field**
- **PCMM Classifier-DSCP/TOS Mask**
- **PCMM Classifier-Priority**
- **PCMM Classifier-ProtocolId**

- **PCMM Classifier-Source Address**
- **PCMM Classifier-Source Port**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Distinguishes between different types of PCMM classifier parameters.

where the codec name for the flow *matches one of specified codec name(s)*

Mode

Cable, Wireless

Syntax

where the codec name *matches-op value-list*

Parameters***matches-op***

One of the following:

- **matches one of** (default)
- **does not match any of**

value-list

A comma-delimited list of values to compare against.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Selects protocol messages based on the codecs in the flow.

Example 35-11 Example

where the codec name for the flow *matches one of AMR-WB*

where the corresponding enforcement session *supports* feature *name*

Mode

Wireless

Syntax

where the corresponding enforcement session *action* feature *value-list*

Parameters***action***

Select one of the following :

- **supports** (default)
- **does not support**

value-list

A comma-delimited list of values to compare against.

This list can contain one or more supported feature. To use a wildcard match pattern, select **Evaluate as Expression**. Wildcard match patterns use the following characters:

- * (asterisk) character to match zero or more characters
- ? (question mark) character to match exactly one character

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Evaluates the feature name in the enforcement session that correlates to the corresponding application (Rx) request.

Example 35-12 Example

where the corresponding enforcement session *supports* feature *GroupComService*.

where the DPI session is a *Gx Lite* session

Mode

Wireless

Syntax

where the DPI session is *dpi-session*

Parameters

dpi-session

One of the following:

- a **Gx Lite session** (default)
- a **Gx Plus session**
- a **SCE Gx session**
- a **TDF Solicit SD session**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Distinguishes between types of DPI sessions.

where the enforcement session is *an IP-CAN session*

Mode

Wireless

Syntax

where the enforcement session is *enforcement-session-type*

Parameters

enforcement-session-type

One or more of the following:

- an **IP-CAN session** (default) — a Gx session
- a **gateway control session** — a Gxx session
- a **DPI enforcement session** — a Gx-Lite or Sd session
- an **S9 sub-session** — an S9 session



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Distinguishes between different types of enforcement sessions.

Example 35-13 Example

```
where the request is creating a new session  
And where the session is an enforcement session  
And where the enforcement session is an S9 sub session  
install EPS2-ims PCC rule(s) for session  
accept message
```

where the event trigger is one of *specified trigger(s)*

Mode

Wireless

Syntax

where the event trigger is one of *event-trigger*

Parameters***event-trigger***

One or more of the following:

- **SGSN_CHANGE**
- **LOSS_OF_BEARER**
- **RECOVERY_OF_BEARER**
- **GW_PCEF_MALFUNCTION**
- **MAX_NR_BEARERS_REACHED**
- **QOS_CHANGE_EXCEEDING_AUTHORIZATION**
- **RAI_CHANGE**
- **USER_LOCATION_CHANGE**
- **OUT_OF_CREDIT**
- **REALLOCATION_OF_CREDIT**
- **REVALIDATION_TIMEOUT**
- **UE_IP_ADDRESS_ALLOCATE**
- **UE_IP_ADDRESS_RELEASE**
- **DEFAULT_EPS_BEARER_QOS_CHANGE**
- **AN_GW_CHANGE**
- **SUCCESSFUL_RESOURCE_ALLOCATION**
- **APPLICATION_START**

- APPLICATION_STOP
- ADC_REVALIDATION_TIMEOUT
- CHARGING_CORRELATION_EXCHANGE
- CREDIT_MANAGEMENT_SESSION_FAILURE
- ACCESS_NETWORK_INFO_REPORT
- QOS_CHANGE
- RAT_CHANGE
- TFT_CHANGE
- PLMN_CHANGE
- IP_CAN_CHANGE
- RESOURCES_LIMITATION
- UE_TIME_ZONE_CHANGE
- USAGE_THRESHOLD_REACHED
- USAGE_REPORT
- TAI_CHANGE
- ECGI_CHANGE
- CELL_CONGESTED
- CELL_CLEAR
- SERVICE_FLOW_DETECTION
- APN_AMBR_MODIFICATION_FAILURE
- USER_CSG_INFORMATION_CHANGE
- DEFAULT_EPS_BEARER_QOS_MODIFICATION_FAILURE
- USER_CSG_HYBRID_SUBSCRIBED_INFORMATION_CHANGE
- USER_CSG_HYBRID_UNSUBSCRIBED_INFORMATION_CHANGE
- HOTSPOT_SHARE_START
- DEFAULT_QOS_CHANGE



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Selects protocol messages based on the event trigger.

Example 35-14 Examples**App Start policy**

where the request is *modifying an existing session*
And where the event trigger is one of *APPLICATION_START*
And where the TDF-Application-Identifier matches one of *TDFID01,TDFID02*
install *pcc_rule1* PCC rule(s) for *session*
continue processing message

App Stop policy

where the request is *modifying an existing session*
And where the event trigger is one of *APPLICATION_STOP*
And where the TDF-Application-Identifier matches one of *TDFID01,TDFID02*
remove *pcc_rule1* PCC rule(s)
continue processing message

where the Filter-Ids in the Final-Unit-Indication AVPs match one or more of *Filter-Ids to match* and the search type is *search type*

Mode

Wireless

Syntax

where the Filter-Ids in the Final-Unit-Indication AVPs match one or more of *value-list* and the search type is *search*

Parameters***value-list***

A comma-delimited list of values to compare against.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

search

One of the following:

- **MATCH_ALL_FROM_ANY_REPORT** (default)
- **MATCH_NONE**
- **MATCH_ANYONE**
- **MATCH_ALL_FROM_ONE_REPORT**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Provides a minimum of at least one Filter-ID in the message that must match the provisioned value or list. Each ID in the provisioned list must match what is in the message.

where the flow has *greater than* # grants per interval

Mode

Cable

Syntax

where the flow has *operator number* grants per interval

Parameters***operator***

One of the following:

- **greater than or equal to**
- **greater than**
- **less than or equal to**
- **less than**
- **equal to**
- **not equal to**

The default for this condition is **greater than**.

number

A numeric value.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Selects protocol messages based on the number of grants per interval in the flow.

where the flow is *an application flow*

Mode

Cable, Wireless

Syntax

where the flow is *flow-type*

Parameters***flow-type***

One or more of the following:

- **an application flow** (default)
- **a UE flow**
- **an application detection flow**
- **the default flow**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Selects protocol messages based on the type of flow:

- An application flow is created based on an application request, such as an Rx AAR message. Application flows are created in the context of an application session (for example, an Rx Media-Sub-Component message). In the context of policy and charging control, corresponding application flows are also created as part of the associated enforcement session (for example, a Gx PCC rule associated with the corresponding Rx Media-Sub-Component message).
- A UE flow is created based on a user equipment-initiated resource request, such as a GPRS PDP context creation or a UE-requested bearer resource modification.
- An application detection flow is created to identify the AVP Application_Detection_Information.
- For the Gx and Rx interfaces, the condition **where flow is the default flow** is deprecated, and always evaluates as false.

where the flow media type is one of *specified type(s)*

Mode

Cable, Wireless

Syntax

where the flow(s) media type is one of *media-type*

Parameters

media-type

One or more of the following, used to determine the type of media:

- **Audio**
- **Video**
- **Data**
- **Application**
- **Control**
- **Text**
- **Message**
- **Other**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Selects protocol messages based on the media type of the flow or flows.

where the flow media type *matches one of user defined media type(s)*

Mode

Wireless

Syntax

where the flow media type *matches-op value-list*

Parameters

matches-op

One of the following:

- **matches one of** (default)
- **does not match any of**

value-list

A comma-delimited list of values to compare against.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Selects one or more protocol messages that match one or more user-defined media types.

where the flow media type *specified type(s)* is one of *specified status(s)*

Mode

Cable

Syntax

where the flow media type *media-type* is one of *media-status*

Parameters***media-type***

One or more of the following, used to determine the type of media:

- **Audio**
- **Video**
- **Data**
- **Application**
- **Control**
- **Text**
- **Message**
- **Other**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

media-status

One or more of the following status type:

- **Enabled**
- **Enabled Uplink**

- **Enabled Downlink**
- **Disabled**
- **Removed**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Selects protocol messages that matches the media type and the status type of the flow.

where the flow packet filter *matches one of specified packet filter(s)*

Mode

Cable, Wireless

Syntax

where the flow packet filter *matches-op value-list*

Parameters***matches-op***

One of the following:

- **matches one of** (default)
- **does not match any of**

value-list

A comma-delimited list of values to compare against.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Selects protocol messages based on the packet filters. The packet filters use IPFilterRule format, as defined in the Diameter base protocol (RFC 3588). For example: `permit in ip from 10.0.0.1 to 10.0.0.2 5060`.

where the flow usage is one of *specified usage(s)*

Mode

Cable, Wireless

Syntax

where the flow usage is *flow-usage-type*

Parameters

flow-usage-type

One or more of the following:

- **No Information**
- **RTCP**
- **AF Signaling**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Selects protocol messages based on the flow usage.

where the IP-CAN bearer is *the primary bearer*

Mode

Wireless

Syntax

where the IP-CAN bearer is *bearer-type*

Parameters

bearer-type

One or more of the following:

- **the primary bearer** (default)
- **a secondary bearer**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Selects protocol messages based on the IP-CAN bearer type.

where the names of the installed PCC/ADC rules *contains one of specified PCC/ADC rule names*

Mode

Wireless

Syntax

where the names of the installed PCC/ADC rules *containment value-list*

Parameters***containment***

One of the following:

- **contains one of** (default)
- **does not contain any of**

value-list

A comma-delimited list of values to compare against.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Determines whether an installed policy and charging control or application detection control rule contains a specified PCC or ADC rule name. See [Managing Traffic Profiles](#) for information on traffic profiles.

where the PCC rule being reinstalled *contains one of specified rule name(s)* and the retry *is* the final attempt

Mode

Wireless

Syntax

where the PCC rule being reinstalled *containment value-list* and the retry *operator-binary* the final attempt

Parameters

containment

One of the following:

- **contains one of** (default)
- **does not contain any of**

value-list

A comma-delimited list of values to compare against.

operator-binary

One of the following:

- **is** (default)
- **is not**

Description

Checks for the presence or absence of one more PCC rules in a session based on the PCC rule names.

where the PCC/ADC rule being reinstalled contains one of *specified rule name(s)* and the retry *is* the final attempt

Mode

Wireless

Syntax

where the PCC/ADC rule being reinstalled contains one of *value-list* and the retry *operator-binary* the final attempt

Parameters

value-list

A comma-delimited list of values to compare against.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

operator-binary

One of the following:

- **is** (default)
- **is not**

Description

Reinstalls the specified policy and charging control or application detection control rule depending on whether this is the final retry attempt or not. See [Managing Traffic Profiles](#) for information on traffic profiles.

where the protocol being executed is *PCMM*

Mode

Cable

Syntax

where the protocol being executed is *protocol*

Parameters

protocol

One of the following:

- **PCMM** (default)
- **Diameter AF**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Distinguishes between protocols being executed.

where the QoS parameters in the flow are equal to *specified value*

Mode

Cable, Wireless

Syntax

where the QoS parameters in the flow are equal to *profile-param*

Parameters***profile-param***

Names of profile parameters that are derived from internal representations of protocol messages. For the specific meaning of the fields, consult the specific protocol specifications.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Selects protocol messages based on values of specific parameters in the protocol message for which there may be an explicit condition. Depending on the parameter chosen, you may be prompted to enter the value to compare against. For QoS parameters that require a bandwidth in bps, refer to [QoS Values for Policy Conditions and Actions](#).

where the QoS upgrade is *supported*

Mode

Wireless

Syntax

where the QoS upgrade is *support-option*

Parameters***support-option***

One of the following

- **not supported**
- **supported** (default)

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Determines whether the QoS upgrade is supported.

where the quota is *requested*

Mode

Wireless

Syntax

where the quota is *quota-change-type*

Parameters***quota-change-type***

One or more of the following:

- **requested** (default)
- **debited**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Selects protocol messages based on the type of change to the quota. See [Managing Quotas](#) for information about defining quotas.

where the quota usage rating conditions changed trigger is one of *specified values*

Mode

Wireless

Syntax

where the quota usage rating conditions changed trigger is one of *trigger-type*

Parameters

trigger-type

One or more of the following:

- **CHANGE_IN_SGSN_IP_ADDRESS**
- **CHANGE_IN_QOS**
- **CHANGE_IN_LOCATION**
- **CHANGE_IN_RAT**
- **CHANGE_IN_QOS_TRAFFIC_CLASS**
- **CHANGE_IN_QOS_RELIABILITY_CLASS**
- **CHANGE_IN_QOS_DELAY_CLASS**
- **CHANGE_IN_QOS_PEAK_THROUGHPUT**
- **CHANGE_IN_QOS_PRECEDENCE_CLASS**
- **CHANGE_IN_QOS_MEAN_THROUGHPUT**
- **CHANGE_IN_QOS_MAXIMUM_BIT_RATE_FOR_UPLINK**
- **CHANGE_IN_QOS_MAXIMUM_BIT_RATE_FOR_DOWNLINK**
- **CHANGE_IN_QOS_RESIDUAL_BER**
- **CHANGE_IN_QOS_SDU_ERROR_RATIO**
- **CHANGE_IN_QOS_TRANSFER_DELAY**
- **CHANGE_IN_QOS_TRAFFIC_HANDLING_PRIORITY**
- **CHANGE_IN_QOS_GUARANTEED_BIT_RATE_FOR_UPLINK**
- **CHANGE_IN_QOS_GUARANTEED_BIT_RATE_FOR_DOWNLINK**
- **CHANGE_IN_LOCATION_MCC**
- **CHANGE_IN_LOCATION_MNC**
- **CHANGE_IN_LOCATION_RAC**
- **CHANGE_IN_LOCATION_LAC**
- **CHANGE_IN_LOCATION_CELL_ID**
- **CHANGE_IN_MEDIA_COMPOSITION**
- **CHANGE_IN_PARTICIPANTS_NMB**
- **CHANGE_IN_THRSHLD_OF_PARTICIPANTS_NMB**
- **CHANGE_IN_USER_PARTICIPATING_TYPE**
- **CHANGE_IN_SERVICE_CONDITION**
- **CHANGE_IN_SERVING_NODE**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Selects protocol messages based on the quota usage rating conditions changed. See [Managing Quotas](#) for information about defining quotas.

where the quota usage reporting reason is one of *specified values*

Mode

Wireless

Syntax

where the quota usage reporting reason is one of *reporting-reason*

Parameters***reporting-reason***

One or more of the following:

- **threshold reached**
- **quota holding time reached**
- **final reporting**
- **quota exhausted**
- **validity time expired**
- **other quota type reported**
- **rating condition changed**
- **forced reauthorization**
- **pool exhausted**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Selects protocol messages based on the quota usage reporting reason. See [Managing Quotas](#) for information about defining quotas.

where the RAN-NAS-Release-Cause is *Protocol Type* and *Cause Type*

Mode

Wireless

Syntax

where the RAN-NAS-Release-Cause is *protocol-type* and *cause-type*

Parameters***protocol-type***

- **S1AP Cause**
- **EMM Cause**
- **ESM Cause**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

cause-type

- **n/a**
- **S1AP - Radio Network Layer**
- **S1AP - Transport Layer**
- **S1AP - NAS**
- **S1AP - Protocol**
- **S1AP - Miscellaneous**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Determines the RAN-NAS-Release-Cause in the request.

where the reauth is triggered by subscriber profile update with notification type *specified type(s)*

Mode

Wireless

Syntax

where the reauth is triggered by subscriber profile update with notification type *specified type(s)*

Parameters***specified type(s)***

One of the following:

- **USER**
- **SUBSCRIBER_POOL**
- **DYNAMIC_QUOTA**
- **POOL_DYNAMIC_QUOTA**
- **ENTITY_STATE**
- **POOL_ENTITY_STATE**
- **QUOTA_ENTITY_USAGE**
- **POOL_QUOTA_ENTITY_USAGE**

Description

Checks whether the RAR is triggered by PNR with changes for the specified type.

Example 35-15 Example

The following policy will release the session if the DATA_LIM for the subscriber is changed from non-zero to zero.

```
where the reauth is triggered by subscriber profile update with
notification type SUBSCRIBER_POOL
And where at least one of pool fields DATA_LIM have been updated
And where the policy context property {Previous.Pool.DATA_LIM} is
numerically greater than 0
release the session
accept message
```

The following policy will ignore an RAR that is triggered by the PNR at user level.

```
where the reauth is triggered by subscriber profile update with
notification type USER
accept message
```

where the reauth request is triggered by scheduled task containing *Service key* with *action*

Mode

Wireless

Syntax

where the reauth request is triggered by scheduled task containing *Service key* with *action* action

Parameters**service**

- **Service**
- **User Session Policy**
- **Billing Day**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

key

Name(s) of a specific entity.

- For Service, the key is a Service Code.
- For User Session Policy, the key is a Policy Code
- For Billing Day, the key is set to any.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

action

The action to take for the service.

- **reset**
- **activate** (default)

- **deactivate**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Determines if the reauth request is triggered by a scheduled task in the specific service using a specific action (activate or deactivate).

where the reauthorization reason is
REASON_REVALIDATION_TIMEOUT

Mode

Wireless

Syntax

where the reauthorization reason is *reason*

Parameters***reason***

One of the following:

- **REASON_DEFAULT**
- **REASON_AUDIT**
- **REASON_TOD**
- **REASON_LI**
- **REASON_RELEASE_SESSION**
- **REASON_POLICY**
- **REASON_NOTIFICATION**
- **REASON_RETRY**
- **REASON_AF**
- **REASON_REVALIDATION_TIMEOUT** (default)
- **REASON_USER_SCHEDULED_TASK**
- **REASON_SY_SESSION_TERMINATION**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Determines the type of RAR message that is used to reset the usage for a quota.

where the reauthorization reason is specified value

Mode

Wireless

Syntax

where the reauthorization reason is *reason*

Parameters***reason***

One of the following:

- **REASON_DEFAULT**
- **REASON_AUDIT**
- **REASON_TOD**
- **REASON_LI**
- **REASON_RELEASE_SESSION**
- **REASON_POLICY**
- **REASON_NOTIFICATION**
- **REASON_RETRY**
- **REASON_AF**
- **REASON_REVALIDATION_TIMEOUT** (default)
- **REASON_USER_SCHEDULED_TASK**
- **REASON_SY_SESSION_TERMINATION_BY_OCS**

**Note:**

If you are using a policy for this parameter, click **User Policy Table**, choose the field (column) representing the parameter.

Description

Determines the type of RAR message that is used to reset the usage for a quota.

where the request AVP Media-Component-Description exists

Mode

Cable, Wireless

Syntax

where the request AVP Media-Component-Description *accessibility*

Parameters

accessibility

One of the following:

- **exists** (default)
- **does not exist**

Description

Determines whether the AVP Media-Component-Description is accessible.

where the request AVP *name* exists

Mode

Wireless

Syntax

where the request AVP *avp* *accessibility*

Parameters

avp

AVP in one of the following formats:

name:vendorID

or a full path

[avp_name1]:vendorID.[avp_name2]:vendorID...

for the members of the grouped AVPs



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

accessibility

One of the following:

- **exists** (default)
- **does not exist**

Description

Checks for the presence or absence of the third-party AVP in an incoming Diameter message.

**Note:**

The condition supports both loaded base Diameter AVPs and third-party AVPs.

where the request AVP *name* value *contains one of value(s)*

Mode

Wireless

Syntax

where the request AVP *avp* value *containment value-list*

Parameters**avp**

AVP in the format:

name:vendorID

or a full path

[avp_name1]:vendorID. [avp_name2]:vendorID...

for the members of the grouped AVPs

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

containment

One of the following:

- **contains one of** (default)
- **does not contain any of**

value-list

A comma-delimited list of values to compare against.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Performs a lookup of the sub-strings in the AVP value. It is possible to check multiple sub-string entries at one time. If the operation type is changed, you can check the opposite scenario, which would not include any of the provided sub-strings.

**Note:**

The condition supports both loaded base Diameter AVPs and third-party AVPs.

where the request AVP *name* value *is* contained in Match Lists *select lists*

Mode

Wireless

Syntax

where the request AVP *avp* value *operator-binary* contained in Match Lists *match-list*

Parameters**avp**

AVP in one of the following formats:

name:vendorID

or a full path

[avp_name1]:vendorID.[avp_name2]:vendorID...

for the members of the grouped AVPs

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

operator-binary

One of the following:

- **is** (default)
- **is not**

match-list

A comma-separated list of values, where each value is a wildcard match pattern that uses the * (asterisk) character to match zero or more characters and the ? (question mark) character to match exactly one character.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Compares the specified AVP value with the values or variables from the specified match list. The condition is where the request AVP name value matches one of the values. The values can be evaluated for equality as well as inequality. To evaluate an AVP value for inequality, the condition **matches one of** must be changed to **does not match any of**.

**Note:**

The condition supports both loaded base Diameter AVPs and third-party AVPs.

where the request AVP *name* value is numerically *equal to value*

Mode

Wireless

Syntax

where the request AVP *avp* value is numerically *operator value*

Parameters

avp

AVP in one of the following formats:

name:vendorID

or a full path

[avp_name1]:vendorID.[avp_name2]:vendorID...

for the members of the grouped AVPs



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

operator

One of the following:

- **greater than or equal to**
- **greater than**
- **less than or equal to**
- **less than**
- **equal to**
- **not equal to**

The default for this condition is **equal to**.

value

String.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Compares a numerical AVP value against a specified number or policy context number variable value.

**Note:**

The condition supports both loaded base Diameter AVPs and third-party AVPs.

where the request AVP *name* value *matches one of value(s)*

Mode

Wireless

Syntax

where the request AVP *avp matches-op value-list*

Parameters***avp***

AVP in one of the following formats:

name:vendorID

or a full path

[avp_name1]:vendorID.[avp_name2]:vendorID...

for the members of the grouped AVPs

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

matches-op

One of the following:

- **matches one of** (default)
- **does not match any of**

value-list

A comma-delimited list of values to compare against.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Compares the specified AVP value with the values or variables from the specified list. The condition is where the request AVP name value matches one of the values. The values can be evaluated for equality as well as inequality. To evaluate an AVP value for inequality, the variable **matches one of** must be changed to **does not match any of**.

**Note:**

The condition supports both loaded base Diameter AVPs and third-party AVPs.

where the request Credit Management Status is one of *specified type(s)*

Mode

Wireless

Syntax

where the request Credit Management Status is one of *credit-management-status*

Parameters***credit-management-status***

One or more of the following:

- **End User Service Denied**
- **Credit Control Not Applicable**
- **Authorization Rejected**
- **User Unknown**
- **Rating Failed**
- **No Gyn Session Service Allowed**
- **No Gyn Session Service Not Allowed**

Description

Selects protocol messages based on whether the Traffic Detection Function (TDF) Credit Management Status field matches one of the selected credit management status options.

Example 35-16 Example

where the request Credit Management Status is one of *End User Service Denied, User Unknown*

where the request is *creating a new flow*

Mode

Cable, Wireless

Syntax

where the request is *change-type*

Parameters***change-type***

One or more of the following:

- **creating a new flow** (default)
- **modifying an existing flow**
- **provisioning a default flow**
- **terminating an existing flow**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Distinguishes between protocol messages based on the type of operation being performed on the flow.

where the request is *creating a new session*

Mode

Cable, Wireless

Syntax

where the request is *request-type*

Parameters

request-type

One or more of the following:

- **creating a new session** (default)
- **modifying an existing session**
- **re-authorizing an existing session**
- **terminating an existing session**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Distinguishes between protocol messages based on the type of operation being performed on the session for the subscriber.

Example 35-17 Examples

App Start policy

```
where the request is modifying an existing session
And where the event trigger is one of APPLICATION_START
And where the TDF-Application-Identifier matches one of TDFID01,TDFID02
install pcc_rule1 PCC rule(s) for session
continue processing message
```

App Stop policy

```
where the request is modifying an existing session
And where the event trigger is one of APPLICATION_STOP
And where the TDF-Application-Identifier matches one of TDFID01,TDFID02
remove pcc_rule1 PCC rule(s)
continue processing message
```

where the request is for *downstream* bandwidth

Mode

Wireline

Syntax

where the request is for *qos-direction* bandwidth

Parameters***qos-direction***

One of the following:

- **upstream** (default)
- **downstream**

Description

Distinguishes between protocol messages based on the direction of bandwidth that is being updated.

where the request is for *reserved* bandwidth

Mode

Cable, Wireless

Syntax

where the request is for *qos-status* bandwidth

Parameters***qos-status***

One of the following:

- **reserved** (default)
- **committed**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Distinguishes between protocol messages based on the type of bandwidth that is being updated.

where the request *is* for *specified class* of traffic

Mode

Cable, Wireline

Syntax

where the request *operator-binary* for *class-of-service* traffic

Parameters

operator-binary

One of the following:

- **is** (default)
- **is not**

class-of-service

Select one or more from the list.

For Cable mode:

- **Best Effort**
- **Non Real-Time Polling**
- **Real-Time Polling**
- **UGS**
- **Background**
- **Conversational**
- **Streaming**
- **Interactive**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Distinguishes between protocol messages based on the class of service for the network traffic that is being updated.

where the request is for *upstream* bandwidth

Mode

Cable, Wireless

Syntax

where the request is for *qos-direction* bandwidth

Parameters

qos-direction

One of the following:

- **upsteam** (default)
- **downsteam**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Distinguishes between protocol messages based on the direction of bandwidth that is being updated.

where the request is reporting session quota usage

Mode

Wireless

Syntax

where the request is reporting session quota usage

Parameters

None

Description

Verifies if the request is reporting usage for the quota on the session level. See [Managing Quotas](#) for information on quotas.

Example 35-18 Example

```
where the request is reporting session quota usage
grant total volume to Min of 20M bytes and 100 percent used for DATA_Plan
using SESS
continue processing message
```

where the request MPS Identifier *matches one of value(s)*

Mode

Cable, Wireless

Syntax

where the MPS Identifier *matches-op value-list*

Parameters

matches-op

One of the following:

- **matches one of** (default)
- **does not match any of**

value-list

A comma-delimited list of values to compare against.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Determines whether the MPS Identifier matches a specified value(s).

where the request *supports* feature *name*

Mode

Wireless

Syntax

where the request *supports* feature *value-list*

Parameters

supports

One of the following:

- **supports** (default)
- **does not support**

value-list

A comma-delimited list of values to compare against.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Determines whether the request supports a specified feature.

where the requested *downstream* bandwidth is *greater than #* and *less than #* bps

Mode

Wireline

Syntax

where the requested *qos-direction* bandwidth is *operator-greater bandwidth* and *operator-less bandwidth* bps

Parameters***qos-direction***

One of the following:

- **upstream** (default)
- **downstream**

operator-greater

One of the following:

- **greater than or equal to**
- **greater than** (default)

bandwidth

A numeric value that specifies bandwidth in bits per second (bps). You can also specify the type to change the rate per second by specifying one of the following:

- **k**—kilobits per second
- **K**—kilobits per second
- **m**—megabits per second
- **M**—megabits per second
- **g**—gigabits per second
- **G**—gigabits per second

operator-less

One of the following:

- **less than or equal to**
- **less than** (default)

Description

Selects protocol messages based on the direction and amount of bandwidth being requested, relative to a numeric value range.

where the requested GCS Identifier *matches one of value(s)*

Mode

Wireless

Syntax

where the requested GCS Identifier *matches-op value-list*

Parameters***matches-op***

One of the following:

- **matches one of** (default)
- **does not match any of**

value-list

A comma-delimited list of values to compare against.

A GCS Identifier value must be formatted as an octet string.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Selects protocol messages based on whether the requested GCS Identifier matches at least one of a list of group communication service values.

Example 35-19 Example

where the requested GCS Identifier *matches one of*
10 FA BB BA 00,11 FA BB BA 00

where the requested guaranteed *downstream* bandwidth is *greater than # bps*

Mode

Wireline

Syntax

where the requested guaranteed *qos-direction bandwidth* is *operator bandwidth bps*

Parameters***qos-direction***

One of the following:

- **upstream** (default)
- **downstream**

bandwidth

A numeric value that specifies bandwidth in bits per second (bps). You can also specify the type to change the rate per second by specifying one of the following:

- **k**—kilobits per second
- **K**—kilobits per second
- **m**—megabits per second
- **M**—megabits per second
- **g**—gigabits per second
- **G**—gigabits per second

operator

One of the following:

- **greater than or equal to**
- **greater than**
- **less than or equal to**
- **less than**
- **equal to**
- **not equal to**

Description

Selects protocol messages based on the amount of bandwidth being requested in a specific direction relative to a numeric value.

where the requested guaranteed *upstream* bandwidth is *greater than* # bps

Mode

Cable, Wireless

Syntax

where the requested guaranteed *flow-direction* bandwidth is *operator bandwidth* bps

Parameters***flow-direction***

One of the following:

- **upstream**
- **downstream**
- **upstream or downstream** (default)

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

operator

One of the following:

- **greater than or equal to**
- **greater than**
- **less than or equal to**
- **less than**
- **equal to**
- **not equal to**

The default for this condition is **greater than**.

bandwidth

A numeric value that specifies bandwidth in bits per second (bps). You can also specify the type to change the rate per second by specifying one of the following:

- **k**—kilobits per second
- **K**—kilobits per second
- **m**—megabits per second
- **M**—megabits per second
- **g**—gigabits per second
- **G**—gigabits per second

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Selects protocol messages based on the amount of bandwidth being requested in a specific direction relative to a numeric value.

where the requested maximum *upstream* bandwidth is *greater than* *specified* bps

Mode

Cable, Wireless

Syntax

where the requested maximum *flow-direction* bandwidth is *operator* *bandwidth* bps

Parameters***flow-direction***

One of the following:

- **upstream**
- **downstream**
- **upstream or downstream** (default)

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

operator

One of the following:

- **greater than or equal to**
- **greater than**
- **less than or equal to**
- **less than**
- **equal to**
- **not equal to**

The default for this condition is **greater than**.

bandwidth

A numeric value that specifies bandwidth in bits per second (bps). You can also specify the type to change the rate per second by specifying one of the following:

- **k**—kilobits per second
- **K**—kilobits per second
- **m**—megabits per second

- **M**—megabits per second
- **g**—gigabits per second
- **G**—gigabits per second

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Selects protocol messages based on the maximum amount of bandwidth being requested in a specific direction relative to a numeric value.

Example 35-20 Example

And

```

    where the request is creating a new session
    where the session is an application session
    where the requested maximum upstream or downstream bandwidth is
    greater than 2400 bps
reject message

```

where the requested media component description reservation priority is one of *specified*

Mode

Cable, Wireless

Syntax

where the requested media component description reservation priority is one of *priority*

Parameters***priority***

One or more of the following:

- **DEFAULT**
- **PRIORITY_ONE**
- **PRIORITY_TWO**
- **PRIORITY_THREE**
- **PRIORITY_FOUR**

- **PRIORITY_FIVE**
- **PRIORITY_SIX**
- **PRIORITY_SEVEN**
- **PRIORITY_EIGHT**
- **PRIORITY_NINE**
- **PRIORITY_TEN**
- **PRIORITY_ELEVEN**
- **PRIORITY_TWELVE**
- **PRIORITY_THIRTEEN**
- **PRIORITY_FOURTEEN**
- **PRIORITY_FIFTEEN**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Selects Rx protocol messages based on the requested media component description reservation priority.

where the requested minimum *upstream* bandwidth is *greater than specified* bps

Mode

Cable, Wireless

Syntax

where the requested minimum *flow-direction* bandwidth is *operator bandwidth* bps

Parameters***flow-direction***

One of the following:

- **upstream**
- **downstream**
- **upstream or downstream** (default)

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

operator

One of the following:

- **greater than or equal to**
- **greater than**
- **less than or equal to**
- **less than**
- **equal to**
- **not equal to**

The default for this condition is **greater than**.

bandwidth

A numeric value that specifies bandwidth in bits per second (bps). You can also specify the type to change the rate per second by specifying one of the following:

- **k**—kilobits per second
- **K**—kilobits per second
- **m**—megabits per second
- **M**—megabits per second
- **g**—gigabits per second
- **G**—gigabits per second

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Selects protocol messages based on the minimum amount of bandwidth being requested in a specific direction relative to a numeric value.

Example 35-21 Example

And

where the request is *creating a new session*

where the session is *an application session*

where the requested minimum *upstream* bandwidth is *greater than*

10000 bps
reject message

where the requested QCI is one of *specified*

Mode

Cable, Wireless

Syntax

where the requested QCI is one of *class-of-service*

Parameters***class-of-service***

One or more of the following:

- **1** (Conversational speech)
- **2** (Conversational)
- **3** (Streaming speech)
- **4** (Streaming)
- **5** (Interactive with priority 1 signalling)
- **6** (Interactive with priority 1)
- **7** (Interactive with priority 2)
- **8** (Interactive with priority 3)
- **9** (Background)
- **65** (Mission critical push-to-talk voice)
- **66** (Push-to-talk voice)
- **69** (Mission critical push-to-talk signalling)
- **70** (Mission critical data)

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Selects protocol messages based on the QoS class identifier (QCI).

where the requested quota is one of *select quota*

Mode

Wireless

Syntax

where the requested quota is one of *quota-name*

Parameters

quota-name

Name(s) of quota defined in the CMP database.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Selects protocol messages based on the requested quotas. See [Managing Quotas](#) for information about defining quotas.

where the requested rating group is one of *select rating group*

Mode

Wireless

Syntax

where the requested rating group is one of *rating-group-name*

Parameters

rating-group-name

Names of rating groups that are defined in the CMP database.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Selects protocol messages based on the subscriber's rating group. See [Managing Services and Rating Groups](#) for information on services.

where the requested service class *matches one of specified name(s)*

Mode

Cable

Syntax

where the requested service class *matches-op service-class-name*

Parameters***matches-op***

One of the following:

- **matches one of** (default)
- **does not match any of**

service-class-name

Names of service classes that are defined in the CMP database or that have been discovered via SNMP.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Selects protocol messages based on the service class name in the request. See [Managing Traffic Profiles](#) for information on service classes.

where the requested services are *select service*

Mode

Wireless

Syntax

where the requested services are *service-profile-name*

Parameters

service-profile-name

Names of service classes that are defined in the CMP database.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Selects protocol messages based on the services in the request. See [Managing Services and Rating Groups](#) for information on services.

where the requested session reservation priority is one of *specified*

Mode

Cable, Wireless

Syntax

where the requested session reservation priority is one of *priority*

Parameters

priority

One or more of the following:

- **DEFAULT**
- **PRIORITY_ONE**
- **PRIORITY_TWO**
- **PRIORITY_THREE**
- **PRIORITY_FOUR**
- **PRIORITY_FIVE**
- **PRIORITY_SIX**
- **PRIORITY_SEVEN**
- **PRIORITY_EIGHT**
- **PRIORITY_NINE**
- **PRIORITY_TEN**
- **PRIORITY_ELEVEN**
- **PRIORITY_TWELVE**

- **PRIORITY_THIRTEEN**
- **PRIORITY_FOURTEEN**
- **PRIORITY_FIFTEEN**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Selects Rx protocol messages based on the requested session reservation priority.

where the requested time limit is *greater than* # seconds

Mode

Cable

Syntax

where the requested time limit is *operator seconds* seconds

Parameters***operator***

One of the following:

- **greater than or equal to**
- **greater than**
- **less than or equal to**
- **less than**
- **equal to**
- **not equal to**

The default for this condition is **greater than**.

seconds

A numeric value that specifies time in units of seconds.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Selects protocol messages based on the specified time limit.

where the requested time limit is unlimited (or unspecified)

Mode

Cable

Syntax

where the requested time limit is unlimited (or unspecified)

Parameters

None

Description

Selects protocol messages that have no time limit.

where the requested *upstream* APN aggregate maximum bitrate is
greater than # bps

Mode

Wireless

Syntax

where the requested *flow-direction* APN aggregate maximum bitrate is
operator bandwidth bps

Parameters

flow-direction

One of the following:

- **upstream**
- **downstream**
- **upstream or downstream** (default)



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

operator

One of the following:

- **greater than or equal to**
- **greater than**
- **less than or equal to**
- **less than**
- **equal to**
- **not equal to**

The default for this condition is **greater than**.

bandwidth

A numeric value that specifies bandwidth in bits per second (bps). You can also specify the type to change the rate per second by specifying one of the following:

- **k**—kilobits per second
- **K**—kilobits per second
- **m**—megabits per second
- **M**—megabits per second
- **g**—gigabits per second
- **G**—gigabits per second

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Selects protocol messages based on the maximum bitrate being requested for an access point name (APN) in a specific direction relative to a numeric value.

where the requested volume limit is *greater than* # kilobytes

Mode

Cable

Syntax

where the requested volume limit is *operator bandwidth* kilobytes

Parameters**operator**

One of the following:

- **greater than or equal to**
- **greater than**
- **less than or equal to**
- **less than**
- **equal to**
- **not equal to**

The default for this condition is **greater than**.

bandwidth

A numeric value that specifies bandwidth in bits per second (bps). You can also specify the type to change the rate per second by specifying one of the following:

- **k**—kilobits per second
- **K**—kilobits per second
- **m**—megabits per second
- **M**—megabits per second
- **g**—gigabits per second
- **G**—gigabits per second

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Selects protocol messages based on the specified volume limit.

where the requested volume limit is unlimited or unspecified

Mode

Cable

Syntax

where the requested volume limit is unlimited or unspecified

Parameters

None

Description

Selects protocol messages that have no volume limit.

where the Required-Access-Info *matches one of value(s)*

Mode

Wireless

Syntax

where the Required-Access-Info *matches-op info*

Parameters***matches-op***

One of the following:

- **matches one of** (default)
- **does not match any of**

info

One or more of the following actions:

- **USER_LOCATION**
- **MS_TIME_ZONE**
- **USER_LOCATION and MS_TIME_ZONE**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

This condition lets you take action based on the value of the Rx Required-Access-Info AVP field.

Example 35-22 Example

where the Required-Access-Info *matches one of USER_LOCATION*

where the roaming profile for the session is one of Roaming Profile *name*

Mode

Wireless

Syntax

where the roaming profile for the session is one of Roaming Profile *profile-name*

Parameters

profile-name

Select a profile name from the list of available Roaming Profiles.

Description

This condition lets you identify the current roaming profile associated with the Rx, Gx or the S9 sub session. See [Managing Roaming Profiles](#) for information on roaming profiles.

where the rule report contains one of *specified rule name(s)* and the final unit action is one of *specified values* and the rule status is *active*

Mode

Wireless

Syntax

where the rule report contains one of *value-list* and the final unit action is one of *action* and the rule status is *field*

Parameters

value-list

A comma-delimited list of values to compare against.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

action

One of the following:

- **TERMINATE**
- **REDIRECT**
- **RESTRICT_ACCESS**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

field

One of the following:

- **active** (default)
- **inactive**
- **temporarily_inactive**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Selects protocol messages based on whether the message contains a specified rule name, reported final unit action, and status received in a rule report.

where the rule report contains one of *specified rule name(s)* and the rule status is *active*

Mode

Wireless

Syntax

where the rule report contains one of *value-list* and the rule status is *field*

Parameters**value-list**

A comma-delimited list of values to compare against.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

field

One of the following:

- **active** (default)
- **inactive**
- **temporarily_inactive**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Selects protocol messages based on whether a rule name and a status was received in a rule report.

where the rule report contains one of *specified rule name(s)* and the rule status is *active* and the rule failure code is one of *specified failure code(s)*

Mode

Wireless

Syntax

where the rule report contains one of *value-list* and the rule status is *field* and the rule failure code is one of *failcode*

Parameters***value-list***

A comma-delimited list of values to compare against.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

field

One of the following:

- **active** (default)
- **inactive**
- **temporarily_inactive**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

failcode

One of the following:

- UNKNOWN_RULE_NAME
- RATING_GROUP_ERROR
- SERVICE_IDENTIFIER_ERROR
- GW_PCEF_MALFUNCTION
- RESOURCES_LIMITATION
- MAX_NR_BEARERS_REACHED
- UNKNOWN_BEARER_ID
- MISSING_BEARER_ID
- MISSING_FLOW_INFORMATION
- RESOURCE_ALLOCATION_FAILURE
- UNSUCCESSFUL_QOS_VALIDATION
- INCORRECT_FLOW_INFORMATION
- PS_TO_CS_HANDOVER
- TDF_APPLICATION_IDENTIFIER_ERROR
- NO_BEARER_BOUND
- FILTER_RESTRICTIONS
- AN_GW_FAILED
- MISSING_REDIRECT_SERVER_ADDRESS
- CM_END_USER_SERVICE_DENIED
- CM_CREDIT_CONTROL_NOT_APPLICABLE
- CM_AUTHORIZATION_REJECTED
- CM_USER_UNKNOWN
- CM_RATING_FAILED

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Selects protocol messages based on whether a rule name or names, status, and failure code are received in a rule report.

where the rule report contains one of *specified rule name(s)* and the rule status is *active* and the rule failure code is one of *specified failure code(s)* and the maximum retry count *is* reached

Mode

Wireless

Syntax

where the rule report contains one of *value-list* and the rule status is *field* and the rule failure code is one of *failcode* and the maximum retry count *operator-binary* reached

Parameters

value-list

A comma-delimited list of values to compare against.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

field

One of the following:

- **active** (default)
- **inactive**
- **temporarily_inactive**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

failcode

One of the following:

- UNKNOWN_RULE_NAME
- RATING_GROUP_ERROR
- SERVICE_IDENTIFIER_ERROR
- GW_PCEF_MALFUNCTION
- RESOURCES_LIMITATION
- MAX_NR_BEARERS_REACHED
- UNKNOWN_BEARER_ID
- MISSING_BEARER_ID
- MISSING_FLOW_INFORMATION
- RESOURCE_ALLOCATION_FAILURE
- UNSUCCESSFUL_QOS_VALIDATION
- INCORRECT_FLOW_INFORMATION
- PS_TO_CS_HANDOVER
- TDF_APPLICATION_IDENTIFIER_ERROR
- NO_BEARER_BOUND
- FILTER_RESTRICTIONS
- AN_GW_FAILED
- MISSING_REDIRECT_SERVER_ADDRESS
- CM_END_USER_SERVICE_DENIED
- CM_CREDIT_CONTROL_NOT_APPLICABLE
- CM_AUTHORIZATION_REJECTED
- CM_USER_UNKNOWN
- CM_RATING_FAILED

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

operator-binary

One of the following:

- **is** (default)
- **is not**

Description

Selects protocol messages based on whether a rule name or names, status, failure code, and the maximum retry count are reached in a rule report. The maximum retry count is the result

of multiplying the Maximum Retry Attempts by the Maximum Retry Cycles (see [Creating a Retry Profile](#) for details on configuring retry attempts).

where the rule report contains RAN-NAS-Release-Cause and is *Protocol Type* and *Cause Type*

Mode

Wireless

Syntax

where the rule report contains RAN-NAS-Release-Cause and is *protocol-type* and *cause-type*

Parameters***protocol-type***

- **S1AP Cause**
- **EMM Cause**
- **ESM Cause**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

cause-type

- **n/a**
- **S1AP - Radio Network Layer**
- **S1AP - Transport Layer**
- **S1AP - NAS**
- **S1AP - Protocol**
- **S1AP - Miscellaneous**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Determines the value of RAN-NAS-Release-Cause in the Charging-Rule-Report.

where the rule report for the flow has status *active*

Mode

Wireless

Syntax

where the rule report for the flow has status *field*

Parameters***field***

One of the following:

- **active** (default)
- **temporarily_inactive**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Tests whether the status of the rule for the flow matches the specified status.

where the *select type* is contained in Match Lists *select lists*

Mode

Wireless

Syntax

where the *field* is contained in Match Lists *match-list*

Parameters***field***

One or more of the following:

- **Serving Gateway Address**—IP address of the serving gateway
- **Requested QCI**—Requested QoS Class Identifier
- **APN**—Access Point Name
- **User Equipment IMEISV**
- **User Equipment MEID**

- **User Equipment ESN**
- **User Equipment MAC**
- **USER IMSI**—User International Mobile Subscriber Identity
- **USER E.164**—User E.164 phone number
- **User SIP URI**—User Session Initiation Protocol Uniform Resource Identifier
- **User NAI**—User Network Access Identifier
- **Endpoint IP Address**—IP address of the endpoint
- **Serving MCC-MNC**—Serving Mobile Country Code, Mobile Network Code
- **Cell Identifier**
- **Location Area Code**—Unique identifier of a LAC
- **Service Area Code**—Unique identifier of a SAC
- **Routing Area Code**—Identifies a routing area within a location area
- **Routing Area Identifier**—Combination of the location area code and routing area code
- **Tracking Area Code**
- **E-UTRAN Cell Identifier**—Identifies cells within a PLMN
- **MPS Identifier**—MPS-Identifier AVP
- **GCS Identifier**—Group Communication Service Identifier
- **AF Application Id**
- **User MCC-MNC**—Identifies a user MCC-MNC
- **Sponsor Identity**—Sponsor identity AVP
- **App Service Provider Id**—Application services provider identity AVP
- **Entitlements**—A defined entitlement
- **TDF Application Identifier**—Identifies an application within PCEF/TDF.
- **NetworkElementDiameterIdentity**—The diameter identity of a network element
- **TWAN_SSID**—The SSID for the trusted WLAN (TWAN), in ASCII string format
- **TWAN_BSSID**—The BSSID for the TWAN, in MAC address format
- **TWAN_PLMNId**—The PLMN identifier for the TWAN, in MCC-MNC address format
- **TWAN_OperatorName**—The Operator Name for the TWAN
- **TWAN_RelayIdentity**—The Relay Identity type for the TWAN, in IP address or FQDN format
- **TWAN_CircuitId**—The relay Circuit ID for the TWAN

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

match-list

A comma-separated list of values, where each value is a wildcard match pattern that uses the * (asterisk) character to match zero or more characters and the ? (question mark) character to match exactly one character.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Selects protocol messages based on whether the messages or associated sessions match any of the values in a match list. Any of the types can be selected in combination. The order will match the list from top to bottom. See [Managing Match Lists](#) for information about defining match lists.

Example 35-23 Example

where the *USER IMSI,LAC,SAC* is contained in Match Lists
Black1,Black2,Black3

where the *select type* is not contained in Match Lists *select lists*

Mode

Wireless

Syntax

where the *field* is not contained in Match Lists *match-list*

Parameters***field***

One or more of the following:

- **Serving Gateway Address**—IP address of the serving gateway
- **Requested QCI**—Requested QoS Class Identifier
- **APN**—Access Point Name

- **User Equipment IMEISV**
- **User Equipment MEID**
- **User Equipment ESN**
- **User Equipment MAC**
- **USER IMSI**—User International Mobile Subscriber Identity
- **USER E.164**—User E.164 phone number
- **User SIP URI**—User Session Initiation Protocol Uniform Resource Identifier
- **User NAI**—User Network Access Identifier
- **Endpoint IP Address**—IP address of the endpoint
- **Serving MCC-MNC**—Serving Mobile Country Code (MCC), Mobile Network Code (MNC)
- **Cell Identifier**
- **Location Area Code**—Unique identifier of a LAC
- **Service Area Code**—Unique identifier of a SAC
- **Routing Area Code**—Identifies a routing area within a location area
- **Routing Area Identifier**—Combination of the location area code and routing area code
- **Tracking Area Code**
- **E-UTRAN Cell Identifier**—Identifies cells within a PLMN
- **MPS Identifier**—MPS-Identifier AVP
- **GCS Identifier**—Group Communication Service Identifier
- **AF Application Id**
- **User MCC-MNC**—User Mobile Country Code (MCC), Mobile Network Code (MNC)
- **Sponsor Identity**—Sponsor identity AVP
- **App Service Provider Id**—Application services provider identity AVP
- **Entitlements**—A defined entitlement
- **NetworkElementDiameterIdentity**—The diameter identity of a network element
- **TDF Application Identifier**—Identifies an application within PCEF/TDF.
- **TWAN_SSID**—The SSID for the trusted WLAN (TWAN), in ASCII string format
- **TWAN_BSSID**—The BSSID for the TWAN, in MAC address format
- **TWAN_PLMNI**—The PLMN identifier for the TWAN, in MCC-MNC address format
- **TWAN_OperatorName**—The Operator Name for the TWAN
- **TWAN_RelayIdentity**—The Relay Identity type for the TWAN, in IP address or FQDN format
- **TWAN_CircuitId**—The relay Circuit ID for the TWAN

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

match-list

A comma-separated list of values, where each value is a wildcard match pattern that uses the * (asterisk) character to match zero or more characters and the ? (question mark) character to match exactly one character.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Selects protocol messages based on whether the messages or associated sessions do not match any of the values in a match list. Any of the types can be selected in combination. The order will match the list from top to bottom. See [Managing Match Lists](#) for information about defining match lists.

Example 35-24 Example

where the *USER IMSI,LAC,SAC* is not contained in Match Lists
BLACK1,BLACK2,BLACK3

where the service info status is one of *specified*

Mode

Cable, Wireless

Syntax

where the service info status is one of *status*

Parameters***status***

One of the following:

- **FINAL_SERVICE_INFORMATION**
- **PRELIMINARY_SERVICE_INFORMATION**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Selects Rx protocol messages based on the service information status.

where the Service-URN is one of *specified value(s)*

Mode

Cable, Wireless

Syntax

where the Service-URN is one of *value-list*

Parameters

value-list

A comma-delimited list of values to compare against.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Selects Rx protocol messages based on the value of the Service-URN field.

where the session is *an enforcement session*

Mode

Cable, Wireless

Syntax

where the session is *session-type*

Parameters

session-type

One of the following:

- **an enforcement session** (default)
- **an application session**
- **a credit control session**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Distinguishes between protocol messages that are operating on different sessions.

where the SessionClassID is *specified value*

Mode

Cable

Syntax

where the SessionClassID is *unit*

Parameters***unit***

A number between 0 and 255.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Selects protocol messages based on the value of the SessionClassID field.

where the specific action is one of *specified action(s)*

Mode

Wireless

Syntax

where the specific action is one of *action*

Parameters

action

One or more of the following actions:

- **SERVICE_INFORMATION_REQUEST**
- **CHARGING_CORRELATION_EXCHANGE**
- **INDICATION_OF_LOSS_OF_BEARER**
- **INDICATION_OF_RECOVERY_OF_BEARER**
- **INDICATION_OF_RELEASE_OF_BEARER**
- **INDICATION_OF_ESTABLISHMENT_OF_BEARER**
- **INDICATION_OF_IP_CAN_CHANGE**
- **INDICATION_OF_OUT_OF_CREDIT**
- **INDICATION_OF_SUCCESSFUL_RESOURCES_ALLOCATION**
- **INDICATION_OF_FAILED_RESOURCES_ALLOCATION**
- **USAGE_REPORT**
- **ACCESS_NETWORK_INFO_REPORT**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

This condition lets you take action based on the value of the Specific-Action AVP field within an Rx RAA message.

where the Sponsor-Identity matches one of *specified Sponsor Identity(s)*

Mode

Wireless

Syntax

where the Sponsor-Identity matches one of *value-list*

Parameters

value-list

A comma-delimited list of values to compare against.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Selects protocol messages based on whether the Sponsored-Identity AVP matches a list of sponsors. This condition supports sponsored data connectivity.

Example 35-25 Example

The following condition is true if the Sponsored-Identity AVP matches either ESPN or FIFA:

where the Sponsor-Identity matches one of *ESPN,FIFA*

where the TDF-Application-Identifier matches one of *specified TDF application id(s)*

Mode

Wireless

Syntax

where the TDF-Application-Identifier matches one of *value-list*

Parameters***value-list***

A comma-delimited list of values to compare against.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Selects protocol messages based on the Traffic Detection Function (TDF) Application Identifier field. A valid TDF application identifier is any string describing the TDF.

Example 35-26 Examples

App Start policy

where the request is *modifying an existing session*

And where the event trigger is one of *APPLICATION_START*

And where the TDF-Application-Identifier matches one of *TDFID01,TDFID02*
install *pcc_rule1* PCC rule(s) for *session*
continue processing message

App Stop policy

where the request is *modifying an existing session*
And where the event trigger is one of *APPLICATION_STOP*
And where the TDF-Application-Identifier matches one of *TDFID01,TDFID02*
remove *pcc_rule1* PCC rule(s)
continue processing message

where the user field *field* is available

Mode

Wireless

Syntax

where the user field *string operator-binary* available

Parameters

string

A string representing the name of a field.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

operator-binary

One of the following:

- **is** (default)
- **is not**

Description

Determines whether a specified user field is available.

where top-up instance being granted for *select type* using *monitoring key* is valid

Mode

Wireless

Syntax

where top-up instance being granted for *select type* using *mon-key operator-binary* valid

Parameters***select type***

Select a data plan.

mon-key

Name(s) of a monitoring key in the CMP database.

operator-binary

One of the following:

- **is** (default)
- **is not**

Description

Determines whether a specified plan is valid for top-up instance.

where the AF-Requested-Data AVP exists and indicates *select type(s)*

Mode

Wireless mode

Syntax

where the AF-Requested-Data AVP exists and indicates *types*

Parameters***types***

The data types available for selection.

Description

Checks for the AF-Requested-Data AVP and specifies the data types.

Example 35-27 Example

This policy example checks the AF request and if the Service-URN and AF-Requested-Data matches then a new traffic profile is installed:

```

where the request is creating a new session
And where the session is an application session
And where the AF-Requested-Data AVP exists and indicates EPC-level
identities required
And where the request AVP Service-URN10415 exists
And where the Service-URN is one of sos
install PCC_Rule_1 PCC rule(s) for session
continue processing message

```


State Variables Conditions

**Note:**

State Variables replace User State Conditions. When upgrading from an earlier release that used State Variable, the properties for User State Conditions are automatically mapped to the corresponding State Variable values. Therefore, the **subscriber** property is mapped to the **subscriber remote** state variable and the **pool** property is mapped to the **pool** state variable.

State Variables are set within a policy action to be used at a later time during policy rule execution (in either conditions or actions). The names of these variables are not predefined and are determined at the time of creation. State variables have a scope which determines how long the value persists after it is set. The scopes are:

- **Subscriber Remote State Variable** — This state variable exists remotely in an SPR as long as the subscriber exists in the SPR. Using this variable requires that an SPR/HSS be configured that is capable of storing this variable.
- **Pool State Variable** — This variable is associated with a quota pool (of multiple subscribers). This variable is stored remotely in an SPR and exists as long as the pool exists in the SPR. Using this variable requires that an SPR/HSS be configured that is capable of storing this variable.
- **Subscriber Local State Variables** — This variable exists locally on the MPE and has a value as long as the associated subscriber has at least one session on that MPE. After the last session is terminated these variables no longer have value and will no longer be available for use in policies.
- **Session State Variables** — This variable has a value that is saved as long as the session the variable is associated with is still valid. After the session is terminated, this variable no longer has value and will no longer be available for use in policies.
- **Policy Evaluation State Variables** — This variable are available for the lifetime of a policy evaluation cycle (the process of evaluating all the policies for a single request or context)

where the last delivery time of *specific use case exists* in the user state variable of LastDeliveryTime

Mode

Wireless mode with SMPP enabled

Wireless-C mode with CMPP enabled.

Syntax

where the last delivery time of *use_case_name accessibility* in the user state variable of LastDeliveryTime

Parameters***use_case_name***

The name of the specific use case to evaluate.

accessibility

One of the following:

- **exists** (default)
- **does not exist**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Verifies the last delivery time of a specific use case exists in the user state variable of *LastDeliveryTime*.

Example 35-28 Example

```

where the request is creating a new session
  And where the enforcement session is an IP-CAN session
  And where the subscriber state variable usrStatus exists
  And where the subscriber state variable usrStatus matches one of `1`
  And where the last delivery time of usecase1 exists in the user state
variable of LastDeliveryTime
reset the last delivery time of usecase1 in the user state variable of
LastDeliveryTime
continue processing message

```

where the scope state variable *name + 0 days rounded up with same granularity is after now* using *configured local time*

Mode

Wireless

Syntax

```

where the scope state variable variable-name direction duration granularity1
rounded rounding with granularity2 granularity is datetime-compare datetime
using time-zone

```

Parameters

scope

One of the following:

- **subscriber**—Subscribers in the remote SPR.
- **pool**—Subscriber pool defined in the SPR.
- **subscriber_local**—Subscribers in the local MPE.
- **session**—Session variables that have a value as long as the session they are associated with is open.
- **policy_evaluation**—Policy evaluation variables that last only for the duration of the policy evaluation cycle.

Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

variable-name

String.

Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

direction

One of the following, indicating a time offset in the future or past:

- **+** (default)
- **-**

duration

Positive integer.

Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

granularity1

The offset is expressed in this granularity

- **days** (default)
- **months**
- **hours**
- **minutes**

rounding

One of the following, indicating rounding up or down:

- **up** (default)
- **down**

granularity2

The calculated date-time is expressed in this granularity:

- **same** (default) — Indicates that the value for *granularity1* is used.
- **months**
- **days**
- **hours**
- **minutes**

datetime-compare

One of the following:

- **after** (default)
- **before**
- **at or before**
- **at or after**

datetime

One of the following:

- A policy variable.
- **now** (default)—The local date-time.
- A date-time in the format: *yyyy-mm-ddThh:mm:ss+UTCOffset*.

 Note:

Enter the date-time directly into the field or click the calendar icon for assistance:

- **Date**—Select the date from the calendar interface.
- **Time**—Select hh:mm:ss.
- **UTC Offset**—Select number of hours before or after UTC time to start.
- **now**—Select for the local date-time.
- **Time only**—Select to use the time only.

- A JavaScript code snippet—Enter a JavaScript statement that evaluates to a date-time in the format: `yyyy-mm-ddThh:mm:ss+UTCoffset`. Click **Evaluate as expression** to bypass date-time format validation.

 Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

time-zone

One of the following:

- **CONFIGURED LOCAL TIME** (default)—Calculate the time from the location configured for this MPE device
- **SYSTEM LOCAL TIME**—Calculate the time from the location of this MPE device
- **USER LOCAL TIME**—Calculate the time from the location configured for the user equipment's location

 Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is evaluated for a state variable based on the result of a comparison between a base date-time value and an offset against either the current date-time or another date-time. If time-zone information is available from the user equipment, time can be calculated from either the MPE device or the user equipment's location.

where the *scope* state variable *name exists*

Mode

Wireless

Syntax

where the *scope* state variable *variable-name accessibility*

Parameters***scope***

One of the following:

- **subscriber**—Subscribers in the remote SPR.
- **pool**—Subscriber pool defined in the SPR.
- **subscriber_local**—Subscribers in the local MPE.
- **session**—Session variables that have a value as long as the session they are associated with is open.
- **policy_evaluation**—Policy evaluation variables that last only for the duration of the policy evaluation cycle.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

variable-name

String.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

accessibility

One of the following:

- **exists** (default)
- **does not exist**

Description

Triggers a policy based on whether or not the specified variable exists within the scope.

where the *scope* state variable *name* is *in* the current billing cycle using *configured local time*

Mode

Wireless

Syntax

where the *scope* state variable *variable-name* is *comparison-op* the current billing cycle using *time-zone*

Parameters***scope***

One of the following:

- **subscriber**—Subscribers in the remote SPR.
- **pool**—Subscriber pool defined in the SPR.
- **subscriber_local**—Subscribers in the local MPE.
- **session**—Session variables that have a value as long as the session they are associated with is open.
- **policy_evaluation**—Policy evaluation variables that last only for the duration of the policy evaluation cycle.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

variable-name

String.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

comparison-op

One of the following:

- **in** (default)

- **not in**
- **before**
- **after**

time-zone

One of the following:

- **CONFIGURED LOCAL TIME** (default)—Calculate the time from the location configured for this MPE device
- **SYSTEM LOCAL TIME**—Calculate the time from the location of this MPE device
- **USER LOCAL TIME**—Calculate the time from the location configured for the user equipment's location

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is evaluated based on the comparison between the timestamp value of the specified state variable and the current billing cycle. If time-zone information is available from the user equipment, time can be calculated from either the MPE device or the user equipment's location.

**Note:**

The quota reset date may vary from the billing cycle end date. If the quota reset cycle is set to more than 1 month, the NextResetTime could be set to a date other than the current billing cycle end date. The billing cycle end date is calculated from the monthly billing cycle.

**Note:**

When the user local time context is in effect, the MPE device ends the billing cycle or resets the quota based on the user local time. If user equipment enters a different time zone near the end of a billing cycle, the subscriber may find that the billing cycle ended earlier than expected, or the service provider may find that the billing cycle ended later than expected.

where the *scope* state variable *name* is numerically *equal to value*

Mode

Wireless

Syntax

where the *scope* state variable *variable-name* is numerically *operator value*

Parameters

scope

One of the following:

- **subscriber**—Subscribers in the remote SPR.
- **pool**—Subscriber pool defined in the SPR.
- **subscriber_local**—Subscribers in the local MPE.
- **session**—Session variables that have a value as long as the session they are associated with is open.
- **policy_evaluation**—Policy evaluation variables that last only for the duration of the policy evaluation cycle.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

variable-name

String.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

operator

One of the following:

- **greater than or equal to**
- **greater than**
- **less than or equal to**
- **less than**
- **equal to**
- **not equal to**

For this condition the default is **equal to**.

value
String.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy based on a numerical comparison between the state variable value and a specified value.

where the *scope* state variable *name* is the current mobile country code

Mode

Wireless

Syntax

where the *scope* state variable *variable-name operator-binary* the current mobile country code

Parameters**scope**

One of the following:

- **subscriber**—Subscribers in the remote SPR.
- **pool**—Subscriber pool defined in the SPR.
- **subscriber_local**—Subscribers in the local MPE.
- **session**—Session variables that have a value as long as the session they are associated with is open.
- **policy_evaluation**—Policy evaluation variables that last only for the duration of the policy evaluation cycle.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

variable-name
String.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

operator-binary

One of the following:

- **is** (default)
- **is not**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is evaluated based on the comparison between the value of the state variable and the current mobile country code.

where the *scope* state variable *name matches one of `value(s)`*

Mode

Wireless

Syntax

where the *scope* state variable *variable-name matches-op `match-list`*

Parameters**scope**

One of the following:

- **subscriber**—Subscribers in the remote SPR.
- **pool**—Subscriber pool defined in the SPR.
- **subscriber_local**—Subscribers in the local MPE.
- **session**—Session variables that have a value as long as the session they are associated with is open.
- **policy_evaluation**—Policy evaluation variables that last only for the duration of the policy evaluation cycle.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

variable-name

String.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

matches-op

One of the following:

- **matches one of** (default)
- **does not match any of**

match-list

A comma-separated list of values, where each value is a wildcard match pattern that uses the * (asterisk) character to match zero or more characters and the ? (question mark) character to match exactly one character.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy based on whether the specified state variable value matches a list of specified values (based on matching wildcard patterns).

where the *scope* state variable *name* value *is* contained in Match Lists
selected lists

Mode

Wireless

Syntax

where the *scope* state variable *variable-name* value *operator-binary* contained in Match Lists *match-list*`

Parameters

scope

One of the following:

- **subscriber**—Subscribers in the remote SPR.
- **pool**—Subscriber pool defined in the SPR.
- **subscriber_local**—Subscribers in the local MPE.
- **session**—Session variables that have a value as long as the session they are associated with is open.
- **policy_evaluation**—Policy evaluation variables that last only for the duration of the policy evaluation cycle.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

variable-name

String.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

operator-binary

One of the following:

- **is** (default)
- **is not**

match-list

A comma-separated list of values, where each value is a wildcard match pattern that uses the * (asterisk) character to match zero or more characters and the ? (question mark) character to match exactly one character.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy based on whether the specified state variable value matches a list of specified values (based on matching wildcard patterns).

Time of Day Conditions

Time-of-Day conditions are related to the time at which the policy rules are being executed.

where the current time *is* between *start time* and *end time* using *configured local time*

Mode

Cable, Wireless, Wireline

Syntax

where the current time *operator-binary* between *time-of-day* and *time-of-day* using *time-zone*

Parameters***operator-binary***

One of the following:

- **is** (default)
- **is not**

time-of-day

A time, in the format of *hh:mm*, where *hh* is a number in the range from 0 to 23.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

time-zone

One of the following:

- **CONFIGURED LOCAL TIME** (default)—Calculate the time from the location configured for this MPE device
- **SYSTEM LOCAL TIME**—Calculate the time from the location of this MPE device
- **USER LOCAL TIME**—Calculate the time from the location configured for the user equipment's location

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy based on time. If time-zone information is available from the user equipment, time can be calculated from either the MPE device or the user equipment's location.

where the current time *is* within the *specified* time period(s)

Mode

Wireless

Syntax

where the current time *operator-binary* within the *time-period* time periods

Parameters***operator-binary***

One of the following:

- **is** (default)
- **is not**

time-period

Names of one or more time periods that are defined in the CMP database.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy based on the time period.

where today is a week day using *configured local time*

Mode

Cable, Wireless, Wireline

Syntax

where today is a week day using *time-zone*

Parameters

time-zone

One of the following:

- **CONFIGURED LOCAL TIME** (default)—Calculate the time from the location configured for this MPE device
- **SYSTEM LOCAL TIME**—Calculate the time from the location of this MPE device
- **USER LOCAL TIME**—Calculate the time from the location configured for the user equipment's location



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy based on the day of the week. If time-zone information is available from the user equipment, time can be calculated from either the MPE device or the user equipment's location.

where today is a weekend day using *configured local time*

Mode

Cable, Wireless

Syntax

where today is a weekend day using *time-zone*

Parameters

time-zone

One of the following:

- **CONFIGURED LOCAL TIME** (default)—Calculate the time from the location configured for this MPE device

- **SYSTEM LOCAL TIME**—Calculate the time from the location of this MPE device
- **USER LOCAL TIME**—Calculate the time from the location configured for the user equipment's location

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy based on the day of the week. If time-zone information is available from the user equipment, time can be calculated from either the MPE device or the user equipment's location.

where *today is day* using *configured local time*

Mode

Cable, Wireless

Syntax

where *today operator-binary day-of-week* using *time-zone*

Parameters***operator-binary***

One of the following:

- **is** (default)
- **is not**

day-of-week

One of the following:

- **Sunday**
- **Monday**
- **Tuesday**
- **Wednesday**
- **Thursday**
- **Friday**
- **Saturday**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

time-zone

One of the following:

- **CONFIGURED LOCAL TIME** (default)—Calculate the time from the location configured for this MPE device
- **SYSTEM LOCAL TIME**—Calculate the time from the location of this MPE device
- **USER LOCAL TIME**—Calculate the time from the location configured for the user equipment's location

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy based on the day of the week. If time-zone information is available from the user equipment, time can be calculated from either the MPE device or the user equipment's location.

where *today* is the specified number(s) th day(s) of Any Month in natural order using configured local time

Mode

Wireless

Syntax

where *today* *operator-binary* the *value-list* th days of *month* in order using *time-zone*

Parameters***operator-binary***

One of the following:

- **is** (default)
- **is not**

value-list

A comma-delimited list of values to compare against.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

month

One or more of the following:

- **January**
- **February**
- **March**
- **April**
- **May**
- **June**
- **July**
- **August**
- **September**
- **October**
- **November**
- **December**

order

Specifies the order to evaluate the value list. The options are:

- **natural order**
- **reverse order**

time-zone

One of the following:

- **CONFIGURED LOCAL TIME** (default)—Calculate the time from the location configured for this MPE device
- **SYSTEM LOCAL TIME**—Calculate the time from the location of this MPE device
- **USER LOCAL TIME**—Calculate the time from the location configured for the user equipment's location

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy based on a day in a month. If time-zone information is available from the user equipment, time can be calculated from either the MPE device or the user equipment's location.

Example 35-29 Example

The following conditions, if evaluated as true, will trigger a policy:

where today is the 1,2,3,4 th days of March, April, May in natural order
using *USER LOCAL TIME*

User Conditions

User conditions are related to the quota pool, subscriber or subscriber account that is associated with the protocol message that triggered the policy rule execution. This includes subscriber-level and account-level tracking of usage. The following conditions are available.

where the account id *matches one of specified id(s)*

Mode

Cable, Wireline

Syntax

where the account id *matches-op match-list*

Parameters***matches-op***

One of the following:

- **matches one of** (default)
- **does not match any of**

match-list

A comma-separated list of values, where each value is a wildcard match pattern that uses the * (asterisk) character to match zero or more characters and the ? (question mark) character to match exactly one character.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is only evaluated for one or more specific user ID values (based on matching wildcard patterns).

where the account will be handling *greater than #* and *less than #* percent of *downstream* limit

Mode

Wireline

Syntax

where the account will be handling *operator-greater percent* and *operator-less percent* percent of *qos-direction* limit

Parameters***operator-greater***

One of the following:

- **greater than or equal to**
- **greater than** (default)

operator-less

One of the following:

- **less than or equal to**
- **less than** (default)

percent

A numeric value.

qos-direction

One of the following:

- **upstream** (default)
- **downstream**

Description

Triggers a policy based on the percent of the bandwidth limit used by the account related to a defined range. This can be further qualified by the direction of the bandwidth. The total is the bandwidth allocated if the request is approved.

where the account will be handling *greater than* # percent of *downstream* limit

Mode

Wireline

Syntax

where the account will be handling *operator* percent percent of *qos-direction* limit

Parameters***operator***

One of the following:

- **greater than or equal to**
- **greater than**
- **less than or equal to**
- **less than**
- **equal to**
- **not equal to**

The default for this condition is **greater than**.

percent

A numeric value.

qos-direction

One of the following:

- **upstream** (default)
- **downstream**

Description

Triggers a policy based on the percent of the bandwidth limit used by the account as it relates to a defined threshold. This can be further qualified by the direction of the bandwidth. The total is the bandwidth allocated if the request is approved.

where the account will be handling *greater than* # percent of *upstream reserved* limit

Mode

Cable

Syntax

where the account will be handling *operator percent percent of qos-direction qos-status* limit

Parameters

operator

One of the following:

- **greater than or equal to**
- **greater than**
- **less than or equal to**
- **less than**
- **equal to**
- **not equal to**

The default for this condition is **greater than**.

percent

An integer value between 0 and 100.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

qos-direction

One of the following:

- **upstream** (default)
- **downstream**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

qos-status

One of the following:

- **reserved** (default)
- **committed**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy based on the percent of the bandwidth limit used by the account as it relates to a defined threshold. This can be further qualified by both the direction and allocation status of the bandwidth. The total is the bandwidth allocated if the request is approved.

where the account will be using *greater than #* and *less than #* bps
downstream bandwidth

Mode

Wireline

Syntax

where the account will be using *operator-greater bandwidth* and *operator-less bandwidth* bps *qos-direction* bandwidth

Parameters***operator-greater***

One of the following:

- **greater than or equal to**
- **greater than** (default)

bandwidth

A numeric value that specifies bandwidth in bits per second (bps). You can also specify the type to change the rate per second by specifying one of the following:

- **k**—kilobits per second
- **K**—kilobits per second
- **m**—megabits per second
- **M**—megabits per second
- **g**—gigabits per second
- **G**—gigabits per second

operator-less

One of the following:

- **less than or equal to**
- **less than** (default)

qos-direction

One of the following:

- **upsteam** (default)
- **downsteam**

Description

Triggers a policy based on the total amount of bandwidth used by the account as it relates to a defined range. This can be further qualified by the direction of the bandwidth. The total is the bandwidth allocated if the request is approved.

where the account will be using *greater than #* and *less than # downstream* sessions

Mode

Wireline

Syntax

where the account will be handling *operator-greater number* and *operator-less number qos-direction* sessions

Parameters**operator-greater**

One of the following:

- **greater than or equal to**
- **greater than** (default)

number

A numeric value.

operator-less

One of the following:

- **less than or equal to**
- **less than** (default)

qos-direction

One of the following:

- **upsteam** (default)
- **downsteam**

Description

Triggers a policy based on the number of sessions for a specific direction of service used by the account as it relates to a defined range. The total is the number of sessions allocated if the request is approved.

where the account will be using *greater than # bps downstream* bandwidth

Mode

Wireline

Syntax

where the account will be using *operator bandwidth bps qos-direction* bandwidth

Parameters***operator***

One of the following:

- **greater than or equal to**
- **greater than**
- **less than or equal to**
- **less than**
- **equal to**
- **not equal to**

The default for this condition is **greater than**.

bandwidth

A numeric value that specifies bandwidth in bits per second (bps). You can also specify the type to change the rate per second by specifying one of the following:

- **k**—kilobits per second
- **K**—kilobits per second
- **m**—megabits per second
- **M**—megabits per second
- **g**—gigabits per second
- **G**—gigabits per second

qos-direction

One of the following:

- **upstream** (default)
- **downstream**

Description

Triggers a policy based on the total amount of bandwidth used by the account as it relates to a defined threshold. This can be further qualified by the direction of the bandwidth. The total is the bandwidth allocated if the request is approved.

where the account will be using *greater than* # bps of *specified class of bandwidth*

Mode

Wireline

Syntax

where the account will be using *operator-greater number* bps of *class-of-service* bandwidth

Parameters

operator-greater

One of the following:

- **greater than or equal to**
- **greater than** (default)

number

A numeric value.

class-of-service

One of the following:

- **Standard Definition**
- **High Definition**

Description

Triggers a policy based on the total amount of bandwidth used by the account as it relates to a defined threshold. This can be further qualified by the class of service of the bandwidth. The total is the amount of bandwidth allocated if the request is approved.

where the account will be using *greater than* # bps *reserved* bandwidth in total for *specified class of* traffic

Mode

Cable

Syntax

where the account will be using *operator bandwidth* bps *qos-status* bandwidth in total for *class-of-service* traffic

Parameters

operator

One of the following:

- **greater than or equal to**
- **greater than**
- **less than or equal to**
- **less than**
- **equal to**
- **not equal to**

The default for this condition is **greater than**.

bandwidth

A numeric value that specifies bandwidth in bits per second (bps). You can also specify the type to change the rate per second by specifying one of the following:

- **k**—kilobits per second
- **K**—kilobits per second
- **m**—megabits per second
- **M**—megabits per second
- **g**—gigabits per second
- **G**—gigabits per second



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

qos-status

One of the following:

- **reserved** (default)
- **committed**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

class-of-service

In Wireless Mode, one (or more) of the following:

- **Background**
- **Conversational**

- **Streaming**
- **Interactive**

In Cable Mode, one (or more) of the following:

- **Best Effort**
- **Non Real-time Polling**
- **Real-time Polling**
- **UGS**
- **Background**
- **Conversational**
- **Streaming**
- **Interactive**

In Wireline Mode, one of the following:

- **Standard Definition**
- **High Definition**

One of the following:

- **Standard Definition**
- **High Definition**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy based on the total amount of bandwidth for specific classes of service used by the associated accounts as it relates to a defined threshold. This can be further qualified by the allocation status of the bandwidth. The total represents the amount of bandwidth that are allocated if the current request is approved.

where the account will be using *greater than #* bps upstream bandwidth in total for *specified application*

Mode

Cable

Syntax

where the account will be using *operator bandwidth* bps upstream bandwidth in total for *app-name*

Parameters

operator

One of the following:

- **greater than or equal to**
- **greater than**
- **less than or equal to**
- **less than**
- **equal to**
- **not equal to**

The default for this condition is **greater than**.

bandwidth

A numeric value that specifies bandwidth in bits per second (bps). You can also specify the type to change the rate per second by specifying one of the following:

- **k**—kilobits per second
- **K**—kilobits per second
- **m**—megabits per second
- **M**—megabits per second
- **g**—gigabits per second
- **G**—gigabits per second



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

app-name

Names of an application. The application must exist in the CMP database.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy based on the total amount of bandwidth allocated for specific applications by the associated account as it relates to a defined threshold. The total represents the

bandwidth that is allocated if the current request is approved. See [Managing Application Profiles](#) for information on applications.

where the account will be using *greater than* # bps upstream reserved bandwidth

Mode

Cable

Syntax

where the account will be using *operator bandwidth bps qos-direction qos-status* bandwidth

Parameters

operator

One of the following:

- **greater than or equal to**
- **greater than**
- **less than or equal to**
- **less than**
- **equal to**
- **not equal to**

The default for this condition is **greater than**.

bandwidth

A numeric value that specifies bandwidth in bits per second (bps). You can also specify the type to change the rate per second by specifying one of the following:

- **k**—kilobits per second
- **K**—kilobits per second
- **m**—megabits per second
- **M**—megabits per second
- **g**—gigabits per second
- **G**—gigabits per second



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

qos-direction

One of the following:

- **upstream** (default)
- **downstream**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

qos-status

One of the following:

- **reserved** (default)
- **committed**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy based on the total amount of bandwidth used by the account as it relates to a defined threshold. This can be further qualified by both the direction and allocation status of the bandwidth. The total is the bandwidth allocated if the request is approved.

where the account will be using *greater than # downstream* sessions

Mode

Wireline

Syntax

where the account will be using *operator number qos-direction* sessions

Parameters**operator**

One of the following:

- **greater than or equal to**
- **greater than**

- **less than or equal to**
- **less than**
- **equal to**
- **not equal to**

The default for this condition is **greater than**.

number

A numeric value.

qos-direction

One of the following:

- **upstream** (default)
- **downstream**

Description

Triggers a policy based on the total number of sessions used by the associated account as it relates to a defined threshold. This can be further qualified by the direction of the sessions. The total represents the number of sessions that are allocated if the current request is approved.

where the account will be using *greater than* # reserved flows in total for *specified class of traffic*

Mode

Cable

Syntax

where the account will be using *operator number qos-status* flows in total for *class-of-service* traffic

Parameters

operator

One of the following:

- **greater than or equal to**
- **greater than**
- **less than or equal to**
- **less than**
- **equal to**
- **not equal to**

The default for this condition is **greater than**.

number

A numeric value.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

qos-status

One of the following:

- **reserved** (default)
- **committed**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

class-of-service

In Wireless Mode, one (or more) of the following:

- **Background**
- **Conversational**
- **Streaming**
- **Interactive**

In Cable Mode, one (or more) of the following:

- **Best Effort**
- **Non Real-time Polling**
- **Real-time Polling**
- **UGS**
- **Background**
- **Conversational**
- **Streaming**
- **Interactive**

In Wireline Mode, one of the following:

- **Standard Definition**
- **High Definition**

One of the following:

- **Standard Definition**

- **High Definition**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy based on the total number of flows for specific classes of service used by the associated accounts as it relates to a defined threshold. This can be further qualified by the allocation status of the flows. The total represents the number of flows that are allocated if the current request is approved.

where the account will be using *greater than # specified class of sessions*

Mode

Wireline

Syntax

where the account will be using *operator-greater number class-of-service sessions*

Parameters***operator-greater***

One of the following:

- **greater than or equal to**
- **greater than** (default)

number

A numeric value.

class-of-service

One of the following:

- **Standard Definition**
- **High Definition**

Description

Triggers a policy based on the total number of sessions for specific classes of service used by the account as it relates to a defined threshold. This can be further qualified by the class of the sessions. The total is the number of sessions allocated if the request is approved.

where the account will be using *greater than* # upstream flows in total for *specified application*

Mode

Cable

Syntax

where the account will be using *operator number* upstream flows in total for *app-name*

Parameters***operator***

One of the following:

- **greater than or equal to**
- **greater than**
- **less than or equal to**
- **less than**
- **equal to**
- **not equal to**

The default is **greater than**.

number

A numeric value.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

app-name

Names of an application. The application must exist in the CMP database.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy based on the total number of flows for specific applications used by the associated accounts as it relates to a defined threshold. The total represents the number of flows that are allocated if the current request is approved. See [Managing Application Profiles](#) for information on applications.

where the account will be using *greater than* # *upstream reserved* flows

Mode

Cable

Syntax

where the account will be using *operator number qos-direction qos-status* flows

Parameters

operator

One of the following:

- **greater than or equal to**
- **greater than**
- **less than or equal to**
- **less than**
- **equal to**
- **not equal to**

The default for this condition is **greater than**.

number

A numeric value.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

qos-direction

One of the following:

- **upstream** (default)
- **downstream**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

qos-status

One of the following:

- **reserved** (default)
- **committed**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy based on the total number of flows used by the associated account as it relates to a defined threshold. This can be further qualified by both the direction and allocation status of the flows. The total represents the number of flows that are allocated if the current request is approved.

where the pool type is *basic*

Mode

Wireless

Syntax

where the pool type is *pool-type*

Parameters**pool-type**

Select one of the following:

- **basic**
- **enterprise**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is only evaluated if the pooled quota group type matches the selected type.

Example 35-30 Example

where the pool type is *enterprise*

where the *subscriber or pool* does not have any of the *named* entitlements

Mode

Wireless

Syntax

where the *subscriber* does not have any of the *value-list* entitlements

Parameters***subscriber***

One of the following:

- **subscriber** (default)—Individual subscriber
- **pool**—Subscriber pool defined on the SPR

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

value-list

A comma-delimited list of values to compare against.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is evaluated as true for users who do not have any of the specified entitlements. The user must have none of the entitlements in the specified list. See the *CMP Wireless User's Guide* for information on entitlements.

where the *subscriber or pool* does not have at least one of the *named* entitlements

Mode

Wireless

Syntax

where the *subscriber* does not have at least one of the *value-list* entitlements

Parameters***subscriber***

One of the following:

- **subscriber** (default)—Individual subscriber
- **pool**—Subscriber pool defined on the SPR

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

value-list

A comma-delimited list of values to compare against.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is evaluated as true for users who do not have all of the specified entitlements. False if the user has all of the entitlements in the specified list. See the *CMP Wireless User's Guide* for information on entitlements.

where the *subscriber or pool field + 0 days rounded up with same granularity is after now using configured local time*

Mode

Wireless

Syntax

where the *subscriber field-name direction duration granularity1 rounded rounding with granularity2 granularity is datetime-compare datetime using time-zone*

Parameters

subscriber

One of the following:

- **subscriber** (default)—Individual subscriber
- **pool**—Subscriber pool defined on the SPR



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

field-name

String representing a datetime.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

direction

One of the following, indicating a time offset in the future or past:

- **+** (default)

- -

duration

Positive integer.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

granularity1

The calculated datetime is expressed in this granularity:

- **days** (default)
- **months**
- **hours**
- **minutes**

rounding

One of the following, indicating rounding up or down:

- **up**
- **down**

granularity2

Rounding, either up or down, is expressed in this granularity:

- **same** (same as *granularity1*)
- **months**
- **days**
- **hours**
- **minutes**

datetime-compare

One of the following:

- **after** (default)
- **before**
- **at or before**
- **at or after**

datetime

One of the following:

- A policy variable.
- **now** (default)—The local date-time.

- A date-time in the format: `yyyy-mm-ddThh:mm:ss+UTCOffset`.

 Note:

Enter the date-time directly into the field or click the calendar icon for assistance:

- **Date**—Select the date from the calendar interface.
- **Time**—Select hh:mm:ss.
- **UTC Offset**—Select number of hours before or after UTC time to start.
- **now**—Select for the local date-time.
- **Time only**—Select to use the time only.

- A JavaScript code snippet—Enter a JavaScript statement that evaluates to a date-time in the format: `yyyy-mm-ddThh:mm:ss+UTCOffset`. Click **Evaluate as expression** to bypass date-time format validation.

 Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

time-zone

One of the following:

- **CONFIGURED LOCAL TIME** (default)—Calculate the time from the location configured for this MPE device
- **SYSTEM LOCAL TIME**—Calculate the time from the location of this MPE device
- **USER LOCAL TIME**—Calculate the time from the location configured for the user equipment's location

 Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is evaluated based on the result of a comparison between a base date-time value and an offset against either the current date and time or another date-time for the subscriber or subscriber pool. If time-zone information is available from the user equipment, time can be calculated from either the MPE device or the user equipment's location.

Example 35-31 Example

where the *FamilyPlanGold PromoEnrollTime + 10 days* rounded up with same granularity is before now using configured local time

where the *subscriber or pool* field exists

Mode

Wireless

Syntax

where the *subscriber fieldname accessibility*

Parameters***subscriber***

One of the following:

- **subscriber** (default)—Individual subscriber
- **pool**—Subscriber pool defined on the SPR

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

fieldname

String.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

accessibility

One of the following:

- **exists** (default)
- **does not exist**

Description

Triggers a policy that is evaluated if the specified field either exists or does not exist within the subscriber or subscriber pool data.

where the *subscriber or pool field* is in the current billing cycle using *configured local time*

Mode

Wireless

Syntax

where the *subscriber field-name* is *comparison-op* the current billing cycle using *time-zone*

Parameters***subscriber***

One of the following:

- **subscriber** (default)—Individual subscriber
- **pool**—Subscriber pool defined on the SPR

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

field-name

String.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

comparison-op

One of the following:

- **in** (default)
- **not in**
- **before**
- **after**

time-zone

One of the following:

- **CONFIGURED LOCAL TIME** (default)—Calculate the time from the location configured for this MPE device
- **SYSTEM LOCAL TIME**—Calculate the time from the location of this MPE device
- **USER LOCAL TIME**—Calculate the time from the location configured for the user equipment's location

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is evaluated based on the comparison of the specified timestamp value and the current billing cycle for the subscriber or subscriber pool. If time-zone information is available from the user equipment, time can be calculated from either the MPE device or the user equipment's location.

**Note:**

The quota reset date may vary from the billing cycle end date. If the quota reset cycle is set to more than 1 month, the NextResetTime could be set to a date other than the current billing cycle end date. The billing cycle end date is calculated from the monthly billing cycle.

**Note:**

When the user local time context is in effect, the MPE device ends the billing cycle or resets the quota based on the user local time. If user equipment enters a different time zone near the end of a billing cycle, the subscriber may find that the billing cycle ended earlier than expected, or the service provider may find that the billing cycle ended later than expected.

where the *subscriber or pool field* is modified via notification

Mode

Wireless

Syntax

where the *subscriber field-name operator-binary* modified via notification

Parameters

subscriber

One of the following:

- **subscriber** (default)—Individual subscriber
- **pool**—Subscriber pool defined on the SPR



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

field-name

String.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

operator-binary

One of the following:

- **is** (default)
- **is not**

Description

Triggers a policy that is evaluated based on the reception of a notification of a change to the subscriber or subscriber pool field value.

where the *subscriber or pool field* is numerically equal to value

Mode

Wireless

Syntax

where the *subscriber field-name* is numerically *operator* value

Parameters

subscriber

One of the following:

- **subscriber** (default)—Individual subscriber
- **pool**—Subscriber pool defined on the SPR

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

field-name

String.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

operator

One of the following:

- **greater than or equal to**
- **greater than**
- **less than or equal to**
- **less than**
- **equal to**
- **not equal to**

The default for this condition is **equal to**.

value

Integer value in the inclusive range of -9,223,372,036,854,775,808 to 9,223,372,036,854,775,807 (that is, -2^{63} to $2^{63}-1$).

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is evaluated based on the result of a comparison between the value of a specified field and a numerical value for the subscriber or subscriber pool.

Example 35-32 Example

where the *FamilyPlanGold total-session-count* is numerically *less than 5*

where the *subscriber or pool* field matches one of specified value(s)

Mode

Wireless

Syntax

where the *subscriber field-name matches-op match-list*

Parameters***subscriber***

One of the following:

- **subscriber** (default)—Individual subscriber
- **pool**—Subscriber pool defined on the SPR

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

field-name

String.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

matches-op

One of the following:

- **matches one of** (default)
- **does not match any of**

match-list

A comma-separated list of values, where each value is a wildcard match pattern that uses the * (asterisk) character to match zero or more characters and the ? (question mark) character to match exactly one character.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is evaluated based on the result of a comparison between the value of a specified field and a list of specified values (based on matching wildcard patterns) for the subscriber or subscriber pool.

where the *subscriber or pool field* prior to notification *matches one of specified value(s)*

Mode

Wireless

Syntax

where the *subscriber field-name* prior to notification *matches-op match-list*

Parameters***subscriber***

One of the following:

- **subscriber** (default)—Individual subscriber
- **pool**—Subscriber pool defined on the SPR

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

field-name

String.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

matches-op

One of the following:

- **matches one of** (default)
- **does not match any of**

match-list

A comma-separated list of values, where each value is a wildcard match pattern that uses the * (asterisk) character to match zero or more characters and the ? (question mark) character to match exactly one character.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is evaluated based on the result of a comparison between the value of a specified field and a list of specified values (based on matching wildcard patterns) prior to notification for the subscriber or subscriber pool.

where the *subscriber or pool* has all of the *named* entitlements

Mode

Wireless

Syntax

where the *subscriber* has all of the *value-list* entitlements

Parameters**subscriber**

One of the following:

- **subscriber** (default)—Individual subscriber
- **pool**—Subscriber pool defined on the SPR

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

value-list

A comma-delimited list of values to compare against.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is only evaluated for users that have specific entitlements. The user must have all the entitlements in the specified list. See the *CMP Wireless User's Guide* for information on entitlements.

where the *subscriber or pool* has at least one of the *named* entitlements

Mode

Wireless

Syntax

where the *subscriber* has at least one of the *value-list* entitlements

Parameters***subscriber***

One of the following:

- **subscriber** (default)—Individual subscriber
- **pool**—Subscriber pool defined on the SPR

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

value-list

A comma-delimited list of values to compare against.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is evaluated as true for users that have specific entitlements. The user must have one of the entitlements in the specified list. See the *CMP Wireless User's Guide* for information on entitlements.

where the *subscriber or pool* profile data is available

Mode

Wireless

Syntax

where the *subscriber* profile data *operator-binary* available

Parameters***subscriber***

One of the following:

- **subscriber** (default)—Individual subscriber
- **pool**—Subscriber pool defined on the SPR

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

operator-binary

One of the following:

- **is** (default)
- **is not**

Description

Triggers a policy based on whether subscriber or subscriber pool data is or is not available.

where the subscriber profile data *expiration timestamp field for day pass in millis* is less than *hours from expiration* hours from expiring

Mode

Wireless

Syntax

where the subscriber profile data *field-name* is less than *number* hours from expiring

Parameters

field-name

String.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

number

A numeric value.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy based on whether the value of a subscriber profile timestamp field is less than the specified number of hours away.

where the tier *is* one of *specified tier(s)*

Mode

Cable, Wireless, Wireline

Syntax

where the tier *operator-binary* one of *tiers*

Parameters

operator-binary

One of the following:

- **is** (default)
- **is not**

tiers

A comma-separated list of names of one more tiers defined in the CMP database.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is or is not evaluated for one or more specific tiers. See *CMP User Guide* for information on managing tiers.

where the tier will be handling *greater than #* and *less than # specified class of sessions*

Mode

Wireline

Syntax

where the tier will be handling *operator-greater number* and *operator-less number class-of-service session*

Parameters***operator-greater***

One of the following:

- **greater than or equal to**
- **greater than** (default)

number

A numeric value.

operator-less

One of the following:

- **less than or equal to**
- **less than** (default)

class-of-service

One of the following:

- **Standard Definition**
- **High Definition**

Description

Triggers a policy based on the total number of sessions for a specific class of service used by the tier as it relates to a defined range. The total is the number of sessions allocated if the request is approved.

where the tier will be handling *greater than # specified class of sessions*

Mode

Wireline

Syntax

where the tier will be handling *operator-greater number class-of-service sessions*

Parameters***operator-greater***

One of the following:

- **greater than or equal to**
- **greater than** (default)

number

A numeric value.

class-of-service

One of the following:

- **Standard Definition**
- **High Definition**

Description

Triggers a policy based on the total number of sessions for a specific class of service used by the tier as it relates to a defined threshold. The total is the number of sessions allocated if the request is approved.

where the tier will be using *greater than # and less than # bps of specified class of bandwidth*

Mode

Wireline

Syntax

where the tier will be using *operator-greater number and operator-less number bps of class-of-service bandwidth*

Parameters

operator-greater

One of the following:

- **greater than or equal to**
- **greater than** (default)

number

A numeric value.

operator-less

One of the following:

- **less than or equal to**
- **less than** (default)

class-of-service

In Wireless Mode, one (or more) of the following:

- **Background**
- **Conversational**
- **Streaming**
- **Interactive**

In Cable Mode, one (or more) of the following:

- **Best Effort**
- **Non Real-time Polling**
- **Real-time Polling**
- **UGS**
- **Background**
- **Conversational**
- **Streaming**
- **Interactive**

In Wireline Mode, one of the following:

- **Standard Definition**
- **High Definition**

One of the following:

- **Standard Definition**
- **High Definition**

Description

Triggers a policy based on the total amount of bandwidth used by the tier as it relates to a defined range. This can be further qualified by the class of service of the bandwidth. The total is the amount of bandwidth allocated if the request is approved. See *CMP User Guide* for information on managing tiers.

where the tier will be using *greater than* # bps of *specified class of* bandwidth

Mode

Wireline

Syntax

where the tier will be using *operator-greater number* and *operator-less number* bps of *class-of-service* bandwidth

Parameters***operator-greater***

One of the following:

- **greater than or equal to**
- **greater than** (default)

number

A numeric value.

operator-less

One of the following:

- **less than or equal to**
- **less than** (default)

class-of-service

One of the following:

- **Standard Definition**
- **High Definition**

Description

Triggers a policy based on the total amount of bandwidth used by the tier as it relates to a defined threshold. This is further qualified by the class of service of the bandwidth. The total is the amount of bandwidth allocated if the request is approved.

where the user E.164 phone number *matches one of specified number(s)*

Mode

Wireless

Syntax

where the E.164 phone number *matches-op match-list*

Parameters

matches-op

One of the following:

- **matches one of** (default)
- **does not match any of**

match-list

A comma-separated list of values, where each value is a wildcard match pattern that uses the * (asterisk) character to match zero or more characters and the ? (question mark) character to match exactly one character.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is only evaluated for one or more specific E.164 phone numbers (based on matching wildcard patterns). A valid E.164 phone number is any phone number.

where the user has *greater than* # of passes named *select type*

Mode

Wireless

Syntax

where the user has *operator number* of passes named *pass_name*

Parameters

operator

One of the following:

- **greater than or equal to**
- **greater than**
- **less than or equal to**
- **less than**
- **equal to**
- **not equal to**

The default for this condition is **greater than**.

number

A numeric value.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

pass_name

Select a name from the pass selection pop-up.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy based on the number of selected passes.

where the user has *greater than #* of rollover units of type *unit type* for plan *plan name* and usage *usage type*

Mode

Wireless

Syntax

where the user has *operator number* of rollover units of type *unit_type* for plan *plan_name* and usage *usage_type*

Parameters**operator**

One of the following:

- **greater than or equal to**
- **greater than**
- **less than or equal to**
- **less than**
- **equal to**
- **not equal to**

The default for this condition is **greater than**.

number

A numeric value.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

unit_type

One of the following:

- **Time**
- **Volume**
- **Service Specific**
- **Uplink Volume**
- **Downlink Volume**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

plan_name

Select a name from the plan selection pop-up.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

usage_type

One of the following:

- **Limit**
- **Available**
- **Consumed**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy based on the number of rollover units of a selected unit type for a selected plan and selected usage type.

where the user has *greater than* # of top-ups for plan *select type*

Mode

Wireless

Syntax

where the user has *operator number* of top-ups for plan *plan-name*

Parameters***operator***

One of the following:

- **greater than or equal to**
- **greater than**
- **less than or equal to**
- **less than**
- **equal to**
- **not equal to**

The default for this condition is **greater than**.

number

A numeric value.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

plan-name

Select a name from the plan selection pop-up.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy based on the number of top-ups in the selected plan.

where the user IMSI *matches one of specified number(s)*

Mode

Wireless

Syntax

where the user IMSI *matches-op match-list*

Parameters***matches-op***

One of the following:

- **matches one of** (default)
- **does not match any of**

match-list

A comma-separated list of values, where each value is a wildcard match pattern that uses the * (asterisk) character to match zero or more characters and the ? (question mark) character to match exactly one character.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is only evaluated for one or more specific IMSI values (based on matching wildcard patterns). A valid IMSI value is not more than 15 digits, including the mobile country code (3 digits), mobile network code (2 to 3 digits), and the mobile station identification number. For example: 310150123456789.

where the user is a *home* user

Mode

Wireless

Syntax

where the user is a *user-type* user

Parameters***user-type***

One of the following:

- **home**
- **visiting**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Defines the user type. A user is local (home) when the MCC-MNC from the IMSI matches an MCC-MNC configured in the home MCC-MNC match list(s); otherwise, the user is visiting. If the IMSI is not available, the user is deemed local.

where the user is using *greater than # percent* and *less than # percent*
select type of dynamic quota for *selected*

Mode

Wireless

Syntax

where the user is using *operator-greater number percent* and *operator-less number percent* of *service-type* for dynamic *quota-name*

Parameters***operator-greater***

One of the following:

- **greater than or equal to**
- **greater than** (default)



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

operator-less

One of the following:

- **less than or equal to**
- **less than** (default)



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

number

A number with the maximum of 6 decimals within the range: 0-10000.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

service-type

One of the following:

- **time**
- **total volume**
- **uplink volume**
- **downlink volume**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

quota-name

Name(s) of quota defined in the CMP database.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

This condition allows the PCRF to send SMS messages when the user's quota usage reaches a certain usage ratio. It checks to see whether the used service unit (USU) of a dynamic quota of a specified quota profile is within the specified percent range for the specified type. See [Managing Quotas](#) for information on quotas.

where the user is using *greater than # percent select type* of dynamic quota for *selected*

Mode

Wireless

Syntax

where the user is using *operator number percent service-type* of dynamic quota for *quota-name*

Parameters***operator***

One of the following:

- **greater than or equal to**
- **greater than**
- **less than or equal to**
- **less than**
- **equal to**
- **not equal to**

number

A number with the maximum of 6 decimals within the range: 0-10000.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

service-type

One of the following:

- **time**
- **total volume**
- **uplink volume**
- **downlink volume**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

quota-name

Name(s) of quota defined in the CMP database.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

This condition allows the PCRF to send SMS messages when the user's quota usage reaches a certain usage ratio. It checks to see whether the used service unit (USU) of a dynamic quota of a specified quota profile exceeds the specified percent for the specified type. See [Managing Quotas](#) for information on quotas.

where the user is using *greater than* # seconds in total for *selected* quota

Mode

Wireless

Syntax

where the user is using *operatorseconds* seconds in total for *quota-name* quota

Parameters

operator

One of the following:

- **greater than or equal to**
- **greater than**
- **less than or equal to**
- **less than**
- **equal to**
- **not equal to**

The default for this condition is **greater than**.

seconds

A numeric value that specifies time in units of seconds.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

quota-name

Name(s) of quota defined in the CMP database.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy based on the amount of the time-based quota used by the subscriber as it relates to a defined threshold. The total represents the quota that is allocated if the current request is approved. See [Managing Quotas](#) for information on quotas.

where the user is using *greater than* # service-specific units for *selected* quota

Mode

Wireless

Syntax

where the user is using *operator number* service-specific units for *quota-name* quota

Parameters***operator***

One of the following:

- **greater than or equal to**
- **greater than**
- **less than or equal to**
- **less than**
- **equal to**
- **not equal to**

The default for this condition is **greater than**.

number

A numeric value.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

quota-name

Name(s) of quota defined in the CMP database.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy based on the amount of the service-based quota used by the subscriber as it relates to a defined threshold. The total represents the quota that is allocated if the current request is approved. See [Managing Quotas](#) for information on quotas.

where the user is using *greater than* # units of *total volume (bytes)* for *selected* quota

Mode

Wireless

Syntax

where the user is using *operator number* units of *service-unit* for *quota-name*
quota

Parameters

operator

One of the following:

- **greater than or equal to**
- **greater than**
- **less than or equal to**
- **less than**
- **equal to**
- **not equal to**

The default for this condition is **greater than**.

number

A numeric value.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

service-unit

One of the following:

- **time (seconds)**
- **total volume (bytes)**
- **uplink volume (bytes)**

- **downlink volume (bytes)**

quota-name

Name(s) of quota defined in the CMP database.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy based on the amount of the quota used by the subscriber as it relates to a defined threshold. See [Managing Quotas](#) for information on quotas.

Example 35-33 Example

where the user is using *greater than 50000* units of *total volume*
(*bytes*) for *Monthly1,Daily1*

where the user is using *greater than specified* percent and *less than #*
percent of *select type* for *selected quota*

Mode

Wireless

Syntax

where the user is using *operator extended-percent* percent and *operator*
extended-percent percent of *service-type* for *quota-name* quota

Parameters**operator**

One of the following:

- **greater than or equal to**
- **greater than**
- **less than or equal to**
- **less than**
- **equal to**
- **not equal to**

The default for this condition is **greater than** for the first occurrence and **less than** for the second.

extended-percent

An extended, non-integer percentage that can exceed 100 (for example, 102.4%).

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

service-type

One of the following:

- **time**
- **total volume**
- **uplink volume**
- **downlink volume**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

quota-name

Name(s) of quota defined in the CMP database.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy based on the percent of the specific quota used by the subscriber as it relates to a range. The total represents the quota that is allocated if the current request is approved. See [Managing Quotas](#) for information on quotas.

The calculation used to determine the percentage of quota used differs based on if the aggregate quota function is enabled.

- If the aggregate quota function is enabled, the usage calculation uses the subscriber's usage against the quota plan, top-ups, and rollovers.
- If the aggregate quota function is disabled, the usage calculation only uses the quota plan and ignores any top-ups or rollovers.

For more information on the aggregate quota function, see [Creating a Quota Convention](#).

**Note:**

If this condition applies to a quota pass, then the calculation is not affected by the aggregate quota option. Aggregate quota only affects quota plans.

Example 35-34 Example

where the user is using *greater than 80 percent and less than 100 percent of total volume for Monthly1,Daily1*

where the user is using *greater than specified percent of select type for selected quota*

Mode

Wireless

Syntax

where the user is using *operator extended-percent percent of service-type for quota-name quota*

Parameters***operator***

One of the following:

- **greater than or equal to**
- **greater than**
- **less than or equal to**
- **less than**
- **equal to**
- **not equal to**

The default for this condition is **greater than**.

extended-percent

An extended, non-integer percentage that can exceed 100 (for example, 102.4%).

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

service-type

One of the following:

- **time**
- **total volume**
- **uplink volume**
- **downlink volume**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

quota-name

Name(s) of quota defined in the CMP database.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy based on the percent of the specific quota used by the subscriber as it relates to a defined threshold. The total represents the quota that is allocated if the current request is approved. See [Managing Quotas](#) for information on quotas.

The calculation used to determine the percentage of quota used differs based on if the aggregate quota function is enabled.

- If the aggregate quota function is enabled, the usage calculation uses the subscriber's usage against the quota plan, top-ups, and rollovers.
- If the aggregate quota function is disabled, the usage calculation only uses the quota plan and ignores any top-ups or rollovers.

For more information on the aggregate quota option, see [Creating a Quota Convention](#).

**Note:**

If this condition applies to a quota pass, then the calculation is not affected by the aggregate quota option. Aggregate quota only affects quota plans.

Example 35-35 Example

where the user is using *greater than 100* percent of *total volume* for
Monthly1,Daily1

where the user NAI *matches one of specified id(s)*

Mode

Wireless

Syntax

where the user NAI *matches-op match-list*

Parameters***matches-op***

One of the following:

- **matches one of** (default)
- **does not match any of**

match-list

A comma-separated list of values, where each value is a wildcard match pattern that uses the * (asterisk) character to match zero or more characters and the ? (question mark) character to match exactly one character.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is only evaluated for one or more specific NAI values (based on matching wildcard patterns).

where the user realm *matches one of specified realm(s)*

Mode

Wireless

Syntax

where the user realm *matches-op match-list*

Parameters

matches-op

One of the following:

- **matches one of** (default)
- **does not match any of**

match-list

A comma-separated list of values, where each value is a wildcard match pattern that uses the * (asterisk) character to match zero or more characters and the ? (question mark) character to match exactly one character.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is only evaluated for one or more specific realms (based on matching wildcard patterns).

where the user *Service key exists*

Mode

Wireless

Syntax

where the user service key field accessibility

Parameters

service

One of the following:

- **Service**
- **User Session Policy**
- **User Location**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

key

Name(s) of a specific entity.

- For Service, the key is a Service Code.
- For User Session Policy, the key is a Policy Code
- For User Location, the key is a Location Code.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

field

The name of a field belonging to the selected service.

accessibility

One of the following:

- **exists** (default)
- **does not exist**

Description

Determines if the selected service exists.

where the user *Service key field contains one of specified value(s)*

Mode

Wireless

Syntax

where the user *service key field containment value-list*

Parameters

service

- **Service** (default)
- **User Session Policy**
- **User Location**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

key

Name(s) of a specific entity.

- For Service, the key is a Service Code.
- For User Session Policy, the key is a Policy Code
- For User Location, the key is either a Location Code or a Policy Code.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

field

The name of a field belonging to the selected service.

containment

One of the following:

- **contains one of** (default)
- **does not contain any of**

value-list

A comma-delimited list of values to compare against.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Determines if the entity field contains the specified value.

where the user *Service key field matches one of value(s)*

Mode

Wireless

Syntax

where the user *service key field matches-op match-list*

Parameters

service

- **Service**
- **User Session Policy**
- **User Location**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

key

Name(s) of a specific entity:

- For Service, the key is a Service Code
- For User Session Policy, the key is a Policy Code
- For User Location, the key is either a Location Code or a Policy Code



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

field

The name of a field belonging to the selected service.

matches-op

One of the following:

- **matches one of** (default)
- **does not match any of**

match-list

A comma-separated list of values, where each value is a wildcard match pattern that uses the * (asterisk) character to match zero or more characters and the ? (question mark) character to match exactly one character.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy when the specified fields match the selected entity.

where the user *Service key field* prior to notification *matches one of* previous value

Mode

Wireless

Syntax

where the user *service key field* prior to notification *matches-op* previous value

Parameters**service**

- **Service**
- **User Session Policy**
- **User Location**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

key

Name(s) of a specific entity.

- For Service, the key is a Service Code.
- For User Session Policy, the key is a Policy Code
- For User Location, the key is either a Location Code or a Policy Code.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

field

The name of a field belonging to the selected service.

matches-op

One of the following:

- **matches one of** (default)
- **does not match any of**

Description

Determines if the field value of a service changed because of a notification request from SPR.

where the user *Service key* is *in* the activation timeframe using *configured local time*

Mode

Wireless

Syntax

where the user *service key* is *comparison-op* the activation timeframe using *time-zone*

Parameters**service**

- **Service** (default)
- **User Session Policy**
- **User Location**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

key

Name(s) of a specific entity.

- For Service, the key is a Service Code.
- For User Session Policy, the key is a Policy Code
- For User Location, the key is a Location Code.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

comparison-op

One of the following:

- **in** (default)
- **not in**
- **before**
- **after**

time-zone

One of the following:

- **CONFIGURED LOCAL TIME** (default)—Calculate the time from the location configured for this MPE device
- **SYSTEM LOCAL TIME**—Calculate the time from the location of this MPE device
- **USER LOCAL TIME**—Calculate the time from the location configured for the user equipment's location

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Determines if the specific entity is active by comparing the start/end time for the entity with the current time.

where the user SIP URI *matches one of specified URI(s)*

Mode

Wireless

Syntax

where the user SIP URI *matches-op match-list*

Parameters

matches-op

One of the following:

- **matches one of** (default)
- **does not match any of**

match-list

A comma-separated list of values, where each value is a wildcard match pattern that uses the * (asterisk) character to match zero or more characters and the ? (question mark) character to match exactly one character.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is only evaluated for one or more specific SIP URI values (based on matching wildcard patterns).

where the user will be handling *greater than # percent of upstream reserved* limit

Mode

Wireless

Syntax

where the user will be handling *operator percent percent of qos-direction* for *qos-status*

Parameters

operator

One of the following:

- **greater than or equal to**
- **greater than**
- **less than or equal to**
- **less than**
- **equal to**
- **not equal to**

The default for this condition is **greater than**.

percent

An integer value between 0 and 100.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

qos-direction

One of the following:

- **upstream** (default)
- **downstream**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

qos-status

One of the following:

- **reserved** (default)
- **committed**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy based on the percent of the specific quota used by the subscriber as it relates to a defined threshold. The total represents the quota that is allocated if the current request is approved. See [Managing Quotas](#) for information on quotas.

where the user will be using *greater than* # bps reserved bandwidth in total for *specified class of* traffic

Mode

Wireless

Syntax

where the user will be using *operator bandwidth* bps *qos-status* bandwidth in total for *class-of-service* traffic

Parameters***operator***

One of the following:

- **greater than or equal to**
- **greater than**
- **less than or equal to**
- **less than**
- **equal to**
- **not equal to**

The default for this condition is **greater than**.

bandwidth

A numeric value that specifies bandwidth in bits per second (bps). You can also specify the type to change the rate per second by specifying one of the following:

- **k**—kilobits per second
- **K**—kilobits per second
- **m**—megabits per second
- **M**—megabits per second
- **g**—gigabits per second
- **G**—gigabits per second

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

qos-status

One of the following:

- **reserved** (default)
- **committed**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

class-of-service

In Wireless Mode, one (or more) of the following:

- **Background**
- **Conversational**
- **Streaming**
- **Interactive**

In Cable Mode, one (or more) of the following:

- **Best Effort**
- **Non Real-time Polling**
- **Real-time Polling**
- **UGS**
- **Background**
- **Conversational**
- **Streaming**
- **Interactive**

In Wireline Mode, one of the following:

- **Standard Definition**
- **High Definition**

One of the following:

- **Standard Definition**
- **High Definition**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy based on the total amount of bandwidth allocated for specific classes of service by the associated subscriber as it relates to a defined threshold. This can be further qualified by the allocation status of the bandwidth. The total represents the bandwidth that is allocated if the current request is approved.

where the user will be using *greater than* # bps upstream reserved bandwidth

Mode

Wireless

Syntax

where the user will be using *operator bandwidth* bps *qos-direction* *qos-status* bandwidth

Parameters

operator

One of the following:

- **greater than or equal to**
- **greater than**
- **less than or equal to**
- **less than**
- **equal to**
- **not equal to**

The default for this condition is **greater than**.

bandwidth

A numeric value that specifies bandwidth in bits per second (bps). You can also specify the type to change the rate per second by specifying one of the following:

- **k**—kilobits per second
- **K**—kilobits per second
- **m**—megabits per second
- **M**—megabits per second
- **g**—gigabits per second
- **G**—gigabits per second

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

qos-direction

One of the following:

- **upstream** (default)
- **downstream**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

qos-status

One of the following:

- **reserved** (default)
- **committed**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy based on the total amount of bandwidth allocated. This can be further qualified by both the direction and allocation status of the bandwidth. The total represents the bandwidth that is allocated if the current request is approved.

where the user will be using *greater than # bps upstream reserved* bandwidth in total for *specified application*

Mode

Wireless

Syntax

where the user will be using *operator bandwidth bps qos-direction qos-status bandwidth in total for app-name*

Parameters

operator

One of the following:

- **greater than or equal to**
- **greater than**
- **less than or equal to**
- **less than**
- **equal to**
- **not equal to**

The default for this condition is **greater than**.

bandwidth

A numeric value that specifies bandwidth in bits per second (bps). You can also specify the type to change the rate per second by specifying one of the following:

- **k**—kilobits per second
- **K**—kilobits per second
- **m**—megabits per second
- **M**—megabits per second
- **g**—gigabits per second
- **G**—gigabits per second



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

qos-direction

One of the following:

- **upstream** (default)
- **downstream**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

qos-status

One of the following:

- **reserved** (default)
- **committed**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

app-name

Names of an application. The application must exist in the CMP database.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy based on the total amount of bandwidth allocated for specific applications by the associated subscriber as it relates to a defined threshold. This can be further qualified by both the direction and allocation status of the bandwidth. The total represents the bandwidth that is allocated if the current request is approved. See [Managing Application Profiles](#) for information on applications.

where the user will be using *greater than # upstream reserved* flows

Mode

Wireless

Syntax

where the user will be using *operator number qos-direction qos-status* flows

Parameters

operator

One of the following:

- **greater than or equal to**
- **greater than**
- **less than or equal to**
- **less than**
- **equal to**
- **not equal to**

The default for this condition is **greater than**.

number

A numeric value.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

qos-direction

One of the following:

- **upstream** (default)
- **downstream**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

qos-status

One of the following:

- **reserved** (default)
- **committed**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy based on the total number of flows used by the associated subscriber as it relates to a defined threshold. This can be further qualified by both the direction and allocation status of these flows. The total represents the number of flows that are allocated if the current request is approved.

where the user will be using *greater than # upstream reserved* flows in total for *specified application*

Mode

Wireless

Syntax

where the user will be using *operator number qos-direction qos-status* flows in total for *app-name*

Parameters***operator***

One of the following:

- **greater than or equal to**
- **greater than**
- **less than or equal to**
- **less than**
- **equal to**
- **not equal to**

The default for this condition is **greater than**.

number

A numeric value.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

qos-direction

One of the following:

- **upstream** (default)
- **downstream**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

qos-status

One of the following:

- **reserved** (default)
- **committed**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

app-name

Names of an application. The application must exist in the CMP database.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy based on the total number of flows for specific applications used by the associated subscriber as it relates to a defined threshold. This can be further qualified by both the direction and allocation status of the flows. The total represents the number of flows that are allocated if the current request is approved. See [Managing Application Profiles](#) for information on applications.

where the User's Tier *downstream* bandwidth limit is between # bps and # bps

Mode

Wireline

Syntax

where the User's Tier *qos-direction* bandwidth limit is between *bandwidth* bps and *bandwidth* bps

Parameters***qos-direction***

One of the following:

- **upstream**
- **downstream** (default)

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

bandwidth

A numeric value that specifies bandwidth in bits per second (bps). You can also specify the type to change the rate per second by specifying one of the following:

- **k**—kilobits per second
- **K**—kilobits per second
- **m**—megabits per second
- **M**—megabits per second
- **g**—gigabits per second
- **G**—gigabits per second

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is evaluated for a user tier based on the bandwidth limit. This can be further qualified by the direction of the bandwidth. See the appropriate *CMP User's Guide* for information on tiers.

Example 35-36 Example

where the User's Tier *downstream* bandwidth limit is between 2M bps and 25M bps

where the User's Tier *downstream* bandwidth limit is *greater than* # bps

Mode

Wireline

Syntax

where the User's Tier *qos-direction* bandwidth limit is *operator* bandwidth bps

Parameters

qos-direction

One of the following:

- **upstream**
- **downstream** (default)



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

operator

One of the following:

- **greater than or equal to**
- **greater than**
- **less than or equal to**
- **less than**
- **equal to**
- **not equal to**

The default for this condition is **greater than**

bandwidth

A numeric value that specifies bandwidth in bits per second (bps). You can also specify the type to change the rate per second by specifying one of the following:

- **k**—kilobits per second
- **K**—kilobits per second
- **m**—megabits per second
- **M**—megabits per second
- **g**—gigabits per second
- **G**—gigabits per second

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is evaluated for a user tier based on the comparison between the bandwidth limit and a numerical value. This can be further qualified by the direction of the bandwidth. See the appropriate *CMP User's Guide* for information on tiers.

Example 35-37 Example

where the User's Tier *downstream* bandwidth limit is less than or equal to 25M bps

where the User's Tier *upstream* bandwidth limit is between # bps and # bps

Mode

Cable, Wireless

Syntax

where the User's Tier *qos-direction* bandwidth limit is between *bandwidth* bps and *bandwidth* bps

Parameters**qos-direction**

One of the following:

- **upsteam** (default)
- **downsteam**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

bandwidth

A numeric value that specifies bandwidth in bits per second (bps). You can also specify the type to change the rate per second by specifying one of the following:

- **k**—kilobits per second
- **K**—kilobits per second
- **m**—megabits per second
- **M**—megabits per second
- **g**—gigabits per second
- **G**—gigabits per second

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is evaluated for a user tier based on the bandwidth limit. This can be further qualified by the direction of the bandwidth. See the appropriate *CMP User's Guide* for information on tiers.

Example 35-38 Example

where the User's Tier *downstream* bandwidth limit is between 2M bps and 25M bps

where the User's Tier *upstream* bandwidth limit is *greater than* # bps

Mode

Cable, Wireless

Syntax

where the User's Tier *qos-direction* bandwidth limit is *operator bandwidth* bps

Parameters

qos-direction

One of the following:

- **upstream** (default)
- **downstream**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

operator

One of the following:

- **greater than or equal to**
- **greater than**
- **less than or equal to**
- **less than**
- **equal to**
- **not equal to**

The default for this condition is **greater than**

bandwidth

A numeric value that specifies bandwidth in bits per second (bps). You can also specify the type to change the rate per second by specifying one of the following:

- **k**—kilobits per second
- **K**—kilobits per second
- **m**—megabits per second
- **M**—megabits per second
- **g**—gigabits per second
- **G**—gigabits per second



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers a policy that is evaluated for a user tier based on the comparison between the bandwidth limit and a numerical value. This can be further qualified by the direction of the bandwidth. See the appropriate *CMP User's Guide* for information on tiers.

Example 35-39 Example

where the User's Tier *downstream* bandwidth limit is *less than or equal* to 25M bps

Actions for Writing Policy Rules

The policy wizard supports a large number of actions that can be used for constructing policy rules. There are two types of policy-processing actions:

Mandatory actions

This action defines what happens when the current policy is through executing. When you are creating a policy rule in the policy wizard, these actions are displayed at the top of the list of available actions with a radio button that forces you to select only one of these actions.

Optional actions

These are actions executed when the conditions in the policy rule have been met. When you are creating a policy rule in the policy wizard, this is a list of actions that you can add to your policy rule. You can select none, one, several, or up to 40 of these optional actions per rule. However, each action is limited, so that it can be executed only once per policy rule.

In the same way that you can customize conditions by editing parameter values, many of these actions can be customized by specifying parameter values as well.

Actions are listed in alphabetical order. Actions also are affected by the current mode. Therefore, some of the actions documented may not be available in your policy wizard.

Mandatory Policy-Processing Actions

Policy-processing actions define what the Policy Engine should do when the current policy is through executing. The following are the mandatory policy-processing actions; one of these actions must be selected in each policy.

accept message

Mode

Cable, Wireless, Wireline

Syntax

accept message

Parameters

None

Description

After executing the current policy rule, the Policy Engine continues with the normal processing of the protocol message but no further policy rules are evaluated.

break from policy level

Mode

Cable, Wireless

Syntax

```
break from policy level
```

Parameters

None

Description

Stop evaluating the current policy and continue policy evaluation with the next policy at the parent's level. You should use this action only in reference policies.

continue processing message

Mode

Cable, Wireless, Wireline

Syntax

```
continue processing message
```

Parameters

None

Description

After executing the current policy rule, the Policy Engine continues with the next policy rule.

Example 36-1 Example

```
where the request is terminating an existing session  
And where the enforcement session is an IP-CAN session  
send notification to trace log with `### Alert :: Gx Session  
Terminated ###` and severity `Alert`  
continue processing message
```

reject message

Mode

Cable, Wireless, Wireline

Syntax

reject message

Parameters

None

Description

After executing the current policy rule, the Policy Engine terminates all policy-rule processing and rejects the current protocol message. The specific interpretation of rejecting the message varies depending on the associated protocol. For most application-level requests this translates into some type of error being sent back to the application.

reject message with code *`number`*

Mode

Wireless

Syntax

reject message with code *`number`*

Parameters***number***

A numeric value.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

After executing the current policy rule, the MPE device terminates all policy-rule processing and rejects the current protocol message with a specified error code. If the input number is an invalid error code, then the message returns DIAMETER_AUTHORIZATION_REJECTED(5003).

reject message with code *`number`*

Mode

Wireline

Syntax

reject message with code *`number`*

Parameters

number
qos-direction

A numeric value.

This value is an integer from 1 to 2000000000.

Description

After executing the current policy rule, the generated code is propagated back to the VoD server.

reject message with Experimental-Result-Code *`number`* and Vendor-ID *`number`*

Mode

Wireless

Syntax

```
reject message with Experimental-Result-Code `number` and Vendor-ID  
`number`
```

Parameters

number
A numeric value.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

This action applies to Rx requests only. After executing the current policy rule, the message is rejected, including the specified experimental result code and vendor ID AVPs in the AAA message and the trace log. This action supports sponsored data connectivity.

Example 36-2 Example

The following conditions, if evaluated as true, accept sponsored data connectivity, but otherwise reject the message with Experimental-Result-Code 5067 (“UNAUTHORIZED_SPONSORED_DATA_CONNECTIVITY”) and Vendor-ID 10415 (3GPP):

Or

where the Sponsor-Identity matches one of *nba*

```
And where the Application-Service-Provider-Identity matches one of
netmovies
And where the AF-Application-ID matches one of streaming,voip
And where the application is one of af-10.24
continue processing message

reject message with Experimental-Result-Code `5067` and Vendor-ID `10415`
```

skip to next device

Mode

Cable, Wireless

Syntax

```
skip to next device
```

Parameters

None

Description

Stop evaluating policies for the current device and continue policy evaluation with the next device. If there is no next device, policy execution ends.

skip to next flow

Mode

Cable, Wireless

Syntax

```
skip to next flow
```

Parameters

None

Description

Stop evaluating policies for the current flow and continue policy evaluation with the next flow. If there is no next flow, evaluation continues with the next device; if there is no next device, policy execution ends.

Optional Policy-Processing Actions

The following optional policy-processing actions are available.

add custom grouped AVP *name* and send *always*

Mode

Wireless

Syntax

```
add custom grouped AVP name and send send-mode
```

Parameters

name

Select an existing grouped third-party AVP Name and Vender ID, or an AVP name from an existing policy table.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

send-mode

One of the following:

- **always** (default)
- **unless rejected**
- **if rejected**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Add or send new custom grouped AVP to the current reply. A condition can be set specifying that the AVP is always set to send mode. If you are defining a new grouped third party AVP with members, the grouped AVP has to appear first in the policy. If you are adding a new member AVP that does not have its parent AVP added yet, the policy attempts to locate this grouped AVP in the rest of the policy. If you are including a grouped AVP multiple times in the same message, you have to follow the order in which it appears in the message.

add the APP Detection Flow *select scope* to *specified* PCC rules

Mode

Wireless

Syntax

add the APP Detection Flow *flow-type* to *value-list* PCC rules

Parameters

flow-type

Select one of the following options:

- **Flow-information** (default)
- **TDF-Application-Instance-Identifier**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

value-list

A comma-delimited list of values to compare against.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

This action binds the specified TDF-Application-Identifier and TDF-Application-Instance-Identifier information of the current application detection flow to the Policy and Charging Control (PCC) and Application Detection Control (ADC) rules, so that the MPE device can find the mapping. The specified PCC rules must be installed in this Credit Control Answer (CCA), or the PCC rules are ignored and not installed.

When **Flow-Information** is specified, the TDF-Application-Identifier and TDF-Application-Instance-Identifier information of the current application detection flow is recorded in the MPE device that is associated with the PCC rules. During this process, the MPE device removes related rules while reporting Application-Detection-Information with TDF-Application-Identifier and TDF-Application-Instance-Identifier for an application stop . The Flow-Information is added to the specified PCC rules if select scope is Flow-Information. And do not add duplicated Flow.

When **TDF-Application-Instance-Identifier** is specified, the TDF-Application-Identifier and TDF-Application-Instance-Identifier information of the current application detection flow is recorded in the MPEdevice that is associated with the PCC rules. During this process, the MPE device removes related rules while reporting Application-Detection-Information with TDF-Application-Identifier and TDF-Application-Instance-Identifier for an application stop.

Advanced: set values for QoS and Charging parameters to *specified value*

Mode

Cable, Wireless

Syntax

Advanced: set values for QoS and Charging parameters to *profile-param*

Parameters

profile-param

Names of profile parameters that are derived from internal representations of protocol messages. This list is lengthy and subject to change as new protocols are supported, and therefore is not given here. The policy wizard includes a customized dialog to help you in the selection of parameters and valid values for them. For the specific meaning of the fields it may be necessary to consult protocol specifications. Some values may require extended QoS values, refer to [QoS Values for Policy Conditions and Actions](#) for more information.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Overwrites the corresponding settings in the current protocol message. If you specify settings that are not relevant in the current protocol message, the settings are stored for an upcoming relevant message. For example, if you use this action to set session parameters for a Gx session when an Rx request is received, the settings will not be relevant for the current Rx protocol message and will be stored for an upcoming Gx protocol message.

Example

This is the sequence of steps within the policy wizard needed to specify the following action:

Advanced: set values for QoS and Charging Parameters to *Diameter AF Specific Actions* *INDICATION_OF_LOSS OF BEARER, INDICATION_OF_RECOVERY OF BEARER*

1. In the Actions step, select the optional action **Advanced: set values for QoS and Charging Parameters to specified value**. The action is displayed in the Description section of the page.

Create Policy

Actions: What do you want to do with the message?

Mandatory actions

- ☐ reject message
- ☒ continue processing message
- ☐ accept message
- ☐ skip to next flow
- ☐ skip to next device
- ☐ break from policy level
- ☐ reject message with Experimental-Result-Code `number` and Vendor-ID `number`

Optional actions

- ☐ apply *specified profile(s)* to request
- ☒ Advanced: set values for QoS and Charging parameters to *specified value*

Description (click on an underlined value to edit it):

Advanced: set values for QoS and Charging parameters to specified value
continue processing message

2. In the Description section of the page, click on *specified value*. The Profile Parameter window opens.
3. In the Profile Parameter window, select **Diameter AF Specific Actions**, and click **OK**. You are prompted, Specify the values for the profile parameters:.
4. Use Shift-click or Ctrl-click to select **INDICATION_OF_LOSS_OF_BEARER** and **INDICATION_OF_RECOVERY_OF_BEARER**, and click **Add** to move the values to the list of selected values.

Specify the values for the profile parameters:

Diameter AF Specific Actions

SERVICE_INFORMATION_REQUEST	Add
CHARGING_CORRELATION_EXCHANGE	
INDICATION_OF_RELEASE_OF_BEARER	
INDICATION_OF_ESTABLISHMENT_OF_BE	
INDICATION_OF_IP_CAN_CHANGE	

INDICATION_OF_LOSS_OF_BEARER
INDICATION_OF_RECOVERY_OF_BEARER

Delete

OK Cancel

5. Click **OK**. The action is defined.

Create Policy

Actions: What do you want to do with the message?

Mandatory actions

☐ reject message
☒ continue processing message
☐ accept message
☐ skip to next flow
☐ skip to next device
☐ break from policy level
☐ reject message with Experimental-Result-Code ``number`` and Vendor-ID ``number``

Optional actions

☐ apply *specified profile(s)* to request
☒ Advanced: set values for QoS and Charging parameters to *specified value*

Description (click on an underlined value to edit it):

 Advanced: set values for QoS and Charging parameters to
Diameter AF Specific ActionsINDICATION OF LOSS OF BEARER,INDICATION OF RECOVERY OF BEARER
continue processing message

apply roaming profile *name*

Mode

Wireless

Syntax

apply Roaming Profile *roaming-profile*

Parameters

roaming-profile

The name of the Roaming Profile. For more information on roaming profiles, see [Managing Roaming Profiles](#).



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

This parameter allows you to apply a specific roaming profile.

apply *specified profile(s)* to all flows in the request

Mode

Cable, Wireless

Syntax

apply *traffic-profile* to all flows in the request

Parameters

traffic-profile

One or more traffic profiles. For more information on traffic profiles, see [Managing Traffic Profiles](#).



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

This parameter allows you to choose different traffic profiles to apply to different types of calls.

apply *specified profile(s)* to request

Mode

Cable, Wireless

Syntax

apply *traffic-profile* to request

Parameters

traffic-profile

One or more traffic profiles. For more information on traffic profiles, see [Managing Traffic Profiles](#).



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Overwrites the corresponding settings in the current protocol message. If multiple traffic profiles are selected they are applied in the order in which they are specified. If the traffic profile contains settings that are not relevant in the current protocol message, they are ignored.

apply *specified profiles* to flow(s) whose media type matches one of *specified types*

Mode

Wireless

Syntax

apply *traffic-profile* to flows whose media type matches one of *media-type*

Parameters

traffic-profile

One or more traffic profiles. For more information on traffic profiles, see [Managing Traffic Profiles](#).



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

media-type

One or more of the following, used to determine the type of media:

- **Audio**
- **Video**
- **Data**
- **Application**
- **Control**
- **Text**
- **Message**
- **Other**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Applies one or more traffic profiles to one or more flows of the specified types. Overwrites the corresponding settings in the protocol messages of the specified flows.

If multiple traffic profiles are selected they are applied in the order in which they are specified. If a traffic profile contains settings that are not relevant in the current protocol message, they are ignored. The second parameter lets you apply different traffic profiles to flows of different types.

apply *specified profiles* to selected *specified types* flows in the request

Mode

Cable, Wireless

Syntax

apply *traffic-profile* to selected *media-type* flows in the request

Parameters

traffic-profile

One or more traffic profiles. For more information on traffic profiles, see [Managing Traffic Profiles](#).



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

media-type

One or more of the following, used to determine the type of media:

- **Audio**
- **Video**
- **Data**
- **Application**
- **Control**
- **Text**
- **Message**
- **Other**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Overwrites the corresponding settings in the protocol messages of the specified type. If multiple traffic profiles are selected, they are applied in the order in which they are specified. If the traffic profile contains settings that are not relevant in the current protocol message, they are ignored. The second parameter lets you choose different traffic profiles to apply to different types of calls.

clear alarm with severity *`severity level`*, id *`unique alarm identifier`*
and message *`message text`*

Mode

Cable, Wireless

Syntax

clear alarm with severity *`level`*, id *`alarm-id`* and message *`message`*

Parameters

level

One of the following, used to determine which alarm ID is cleared:

- **Critical** (ID 74000)
- **Major** (ID 74001)
- **Minor** (ID 74002)



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

alarm-id

The alarm ID. If you select **Evaluate as expression**, the text in the field is evaluated as an arithmetic expression, and the result is used.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

message

String. This text may contain policy parameters (described later in this section) to perform parameter substitution within the message text. If you select **Evaluate as**

expression, the text in the field is evaluated as an arithmetic expression, and the result is used.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Clears an alarm on the CMP Active Alarms display containing the specified severity level and message text. This notification is written to the Alarm History Report with severity Clear. To be cleared, a notification must be uniquely identified by severity and alarm ID. For more information, see the appropriate *CMP User's Guide*.

disable forwarding to next hop gateway

Mode

Wireless

Syntax

```
disable forwarding to next hop gateway
```

Parameters

None.

Description

Disables forwarding to the next hop gateway.

disable *monitoring key*

Mode

Wireless

Syntax

```
disable mon-key
```

Parameters***mon-key***

Name(s) of a monitoring key in the CMP database.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Disables usage monitoring from the PCEF. This sets the value of the Usage-Monitoring-Information AVP sent to the MPE device to USAGE_MONITORING_DISABLED. The MPE device will send a usage report. See [Managing Monitoring Keys](#) for information on monitoring keys.

disable VLAN tagging

Mode

Wireless

Syntax

disable VLAN tagging

Parameters

None.

Description

Disables VLAN tagging.

enable event messaging for this request

Mode

Cable

Syntax

```
enable event messaging for this request
```

Parameters

None

Description

Enables event messaging for the current message, using the default Event Messaging parameters for this MPE device. If there is no EventGenerationInfo object in the current message, a new one is added.

enable forwarding to next hop gateway with address *none*

Mode

Wireless

Syntax

```
enable forwarding to next hop gateway with address ip-address
```

Parameters

ip-address

An IPv4 or IPv6 address.

Description

Forwards to the next hop gateway with the specified IP address.

enable subscription for notification of user profile changes

Mode

Wireless

Syntax

```
enable subscription for notification of user profile changes
```

Parameters

None

Description

Causes the MPE device to subscribe to an SPR system for notification of user profile changes.



Note:

Within the same MPE device, if subscription to profile updates (that is, Sh:Notify) has occurred (for example, as a result of a policy action), then the MPE device will not resubscribe to update notifications on subsequent triggers (that is, it will not send additional SNR messages to the SPR system).

enable subtracting usage from *select quota* for *monitoring key*

Mode

Wireless

Syntax

enable/disable subtracting usage from *quota-name* for *mon-key*

Parameters

enable/disable

Select one of the following:

- **enable** (default)
- **disable**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

quota-name

Name(s) of quota defined in the CMP database.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

mon-key

Name(s) of a monitoring key in the CMP database.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Allows or disallows subtraction of the usage reported by the specified monitoring keys from the specified quotas. See [Managing Monitoring Keys](#) for information on monitoring keys.

Example 36-3 Example

In this example, to implement a free promotion, quota granted for a video session is subtracted from the total used at the session level:

```
where the request is creating a new session  
install video PCC rule(s) for session  
grant total volume to 100 percent used for video1 using key2  
grant total volume to 100 percent used for quota1  
enable subtracting usage from quota1 for key2
```

enable VLAN tagging with Id *specified*

Mode

Wireless

Syntax

```
enable VLAN tagging with Id id
```

Parameters***id***

VLAN ID.

Description

Enables VLAN tagging.

enable/disable PRA subscription

Mode

Wireless mode with the 3GPP mode enabled.

Syntax

```
status PRA subscription
```

Parameters***status***

One of the following:

- **enable**
- **disable**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

This action enables or disables PRA subscription.

establish traffic detection session using the IP-CAN TDF information

Mode

Wireless

Syntax

establish traffic detection session using the IP-CAN TDF information

Parameters

None

Description

Use this action to establish an Sd session specified in a Gx CCR request with a single TDF device. On IP-CAN session establishment, the policy action will trigger a TSR command that is sent to the TDF device. This information is received in the TDF-information AVP within the IP-CAN session request.

Example 36-4 Example

```
where the request is creating a new session
And where the session is an enforcement session
And where the enforcement session is an IP-CAN session
establish traffic detection session using the IP-CAN TDF information
continue processing message
```

establish traffic detection session with *select network element identity*

Mode

Wireless

Syntax

establish traffic detection session with *tdf*

Parameters

tdf

One or more TDF network elements defined in the CMP database.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

On a IP-CAN session establishment, the policy action will trigger a TSR command that is sent to the selected TDF device(s) to establish an Sd session.

Example 36-5 Example

```
where the request is creating a new session
And where the session is an enforcement session
And where the enforcement session is an IP-CAN session
establish traffic detection session with tdf1.GalacTel.com,tdf2.GalacTel.com
continue processing message
```

evaluate policy group *select policy group*

Mode

Cable, Wireless

Syntax

```
evaluate policy group group-name
```

Parameters

group-name

Name of a policy group defined in the CMP database.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

If the conditions evaluates to true, evaluate the rules in a policy group. When you click the **select policy group** parameter, a pop-up window opens so you can select an existing policy group.

evaluate policy *select policy*

Mode

Cable, Wireless

Syntax

```
evaluate policy policy-name
```

Parameters

policy-name

Name of a policy defined in the CMP database.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

If the conditions evaluate to true, evaluate a policy. When you click the **select policy parameter**, a pop-up window opens, giving you the choice of selecting an existing policy or creating a new policy. If you click **Create**, a new **Policy Wizard** tab opens so you can create the new policy. When you save the new policy, it is added to the list of policies available for selection at this point.

evaluate the schedule task on *Service*

Mode

Wireless

Syntax

```
evaluate the schedule task on Service
```

Parameters

service

- **Service** (default)

- **User Session Policy**
- **Billing Day**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

If the conditions evaluate to true, evaluate the task.

Example 36-6 Example

```
where notification from Sh datasource is received for Service
And where the user Service 21012501234567890123456789012301
ServiceStartDateTime prior to notification does not match any of previous
value
evaluate the schedule task on Service
accept message
```

fetch Policy Counters *default* from OCS

Mode

Wireless

Syntax

```
fetch Policy Counters counter-name from OCS
```

Parameters***counter-name***

Select one or more policy counter IDs defined in the CMP database; or enter a comma-separated string of policy counter IDs.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Fetches one or more policy counters, by ID, from an online charging server.

grant # bytes for quota

Mode

Wireless

Syntax

```
grant number bytes for quota
```

Parameters

number

A numeric value.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Grants a user the specified number of bytes for the requested service. See [Managing Quotas](#) for information on quotas.

grant # of select units for select quota

Mode

Wireless

Syntax

```
grant number of unit for quota-name
```

Parameters

number

A numeric value.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

unit

One of the following:

- **Seconds**
- **Bytes**
- **Service Specific**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

quota-name

Name(s) of quota defined in the CMP database.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Provisions the usage threshold to the specified number of units for the selected quota profiles. See [Managing Quotas](#) for information on quotas.

Example 36-7 Example

```
grant 40000000 of Bytes for DailyVol,MonthlyVol
```

grant # percent in service-specific units for quota

Mode

Wireless

Syntax

```
grant extended-percent percent in service-specific units for quota
```

Parameters***extended-percent***

An extended, non-integer percentage that can exceed 100 (for example, 102.4%).



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Grants a user the specified percentage of the service-specific unit limit for the requested service.

grant # percent in time for quota

Mode

Wireless

Syntax

```
grant extended-percent percent in time for quota
```

Parameters

extended-percent

An extended, non-integer percentage that can exceed 100 (for example, 102.4%).



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Grants a user the specified percentage of the initial time limit (in seconds) for the requested service.

grant # percent in volume for quota

Mode

Wireless

Syntax

```
grant extended-percent percent in volume for quota
```

Parameters

extended-percent

An extended, non-integer percentage that can exceed 100 (for example, 102.4%).



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Grants a user the specified percentage of the user's volume limit (in bytes) for the requested service.

grant # percent of select type for BEST OF select quota

Mode

Wireless

Syntax

grant extended-percent percent of service-type for BEST OF quota-name

Parameters

extended-percent

An extended, non-integer percentage that can exceed 100 (for example, 102.4%).



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

service-type

One of the following:

- **Time** (Gx only)
- **Volume**
- **Service Specific**
- **Uplink Volume**
- **Downlink Volume**

- **All Volume**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

quota-name

Name(s) of quota defined in the CMP database.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Provisions the usage threshold to the highest available percentage of time, volume, or service-specific quantity of the selected quota profiles. See [Managing Quotas](#) for information on quotas. The best quota is determined using the following rules:

1. Passes are always better than plans
2. Between two passes, the one with the higher priority is better
3. Between two passes with equal priorities, the one with the earlier expiration date is better
4. Between two passes with equal priorities and expiration dates, the one with the earlier purchase date is better

Example 36-8 Example

```
grant 100 percent of remaining on Volume for BEST OF  
GoldDailyVol,GoldWeeklyVol,GoldMonthlyVol
```

grant # percent of select type for select quota

Mode

Wireless

Syntax

```
grant extended-percent percent of type for quota-name
```

Parameters

extended-percent

An extended, non-integer percentage that can exceed 100 (for example, 102.4%).



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

type

One of the following:

- **Time**
- **Volume**
- **Service Specific**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

quota-name

Name(s) of quota defined in the CMP database.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Provisions the usage threshold to the specified percentage of time, volume, or service-specific quantity for the selected quota profile(s). See [Managing Quotas](#) for information on quotas.

Example 36-9 Example

```
grant 100 percent of remaining on Volume for  
GoldDailyVol,GoldWeeklyVol,GoldMonthlyVol
```


grant # seconds for quota

Mode

Wireless

Syntax

```
grant number seconds for quota
```

Parameters

number

A numeric value.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Grants a user the specified amount of time (in seconds) for the requested service. See [Managing Quotas](#) for information on quotas.

grant # service-specific units for quota

Mode

Wireless

Syntax

```
grant number service-specific units for quota
```

Parameters

number

A numeric value.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Grants a user the specified service-specific units for the requested service. See [Managing Quotas](#) for information on quotas.

grant # units of total volume (bytes) for select quota

Mode

Wireless

Syntax

grant number units of service-unit for quota-name

Parameters***volume-type***

One of the following:

- **total** (default)
- **uplink**
- **downlink**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

number

A numeric value.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

service-unit

One of the following:

- **time (seconds)**
- **total volume (bytes)**
- **uplink volume (bytes)**

- **downlink volume (bytes)**

quota-name

Name(s) of quota defined in the CMP database.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Provisions the session quota limit in bytes or seconds for the named quota profile. See [Managing Quotas](#) for information on quotas.

Example 36-10 Example

where the request is *creating a new session*
grant 50000 units of *total volume (bytes)* for *used*

continue processing message

grant # units of *total volume (bytes)* for *select quota* using *monitoring*
key

Mode

Wireless

Syntax

grant *number* units of *service-unit* for *quota-type* using *mon-key*

Parameters

number

A numeric value.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

service-unit

One of the following:

- **time (seconds)**
- **total volume (bytes)**
- **uplink volume (bytes)**
- **downlink volume (bytes)**

quota-type

One of the following:

- **used** (default)—Calculates the quota to grant by subtracting the specified amount in bytes from the initial quota limit minus the quota used so far.
- **initial**—Calculates the quota to grant by subtracting the specified amount in bytes from the initial quota limit.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

mon-key

Name(s) of a monitoring key in the CMP database.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Allows quota profiles to be associated with one or more monitoring keys. This action can be used at the session and rule levels. If two policy actions grant usage for the same monitoring key or usage instance, the last action takes precedence, unless an action grants uplink volume followed by an action that grants downlink volume (or vice versa), in which case the actions are grouped as one action when the message is processed. A policy that grants quota for a monitoring key will overwrite any previous grant of quota for that same monitoring key. This includes any subtraction previously enabled for the same monitoring key. See [Managing Quotas](#) for information on quotas. See [Managing Monitoring Keys](#) for information on monitoring keys.

Example 36-11 Example

```
where the request is creating a new session
grant 50000 units of total volume (bytes) for used using key1

continue processing message
```

grant session time limit to *specified* percent of *select* quota

Mode

Wireless

Syntax

```
grant session time limit to extended-percent percent of quota-name
```

Parameters

extended-percent

An extended, non-integer percentage that can exceed 100 (for example, 102.4%).



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

quota-name

Name(s) of quota defined in the CMP database.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Provisions the session time limit based on a percentage of the time limit, retrieved from up to five named quota profiles. See [Managing Quotas](#) for information on quotas.

grant *total volume* to *specified* percent *used* for BEST OF *select* quota

Mode

Wireless

Syntax

```
grant service-type to extended-percent percent quota-type for BEST OF  
quota-name
```

Parameters

service-type

One of the following:

- **time**
- **total volume**
- **uplink volume**
- **downlink volume**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

extended-percent

An extended, non-integer percentage that can exceed 100 (for example, 102.4%).



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

quota-type

One of the following:

- **used** (default)—Calculates the quota to grant by subtracting the specified amount in bytes from the initial quota limit minus the quota used so far.
- **initial**—Calculates the quota to grant by subtracting the specified amount in bytes from the initial quota limit.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

quota-name

Name(s) of quota defined in the CMP database.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Provisions the usage threshold to the highest available percentage volume or time of the selected quota profiles. See [Managing Quotas](#) for information on quotas. The best quota is determined using the following rules:

1. Passes are always better than plans
2. Between two passes, the one with the higher priority is better
3. Between two passes with equal priorities, the one with the earlier expiration date is better
4. Between two passes with equal priorities and expiration dates, the one with the earlier purchase date is better

Example 36-12 Example

```
where the request is creating a new session
grant total volume to 100 percent used for BEST OF Monthly1,Daily1

continue processing message
```

grant total volume to specified percent used for BEST OF select quota using monitoring key

Mode

Wireless

Syntax

```
grant service-type to extended-percent percent quota-type for BEST OF
quota-name using mon-key
```

Parameters***service-type***

One of the following:

- **time**
- **total volume**
- **uplink volume**
- **downlink volume**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

extended-percent

An extended, non-integer percentage that can exceed 100 (for example, 102.4%).



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

quota-type

One of the following:

- **used** (default)—Calculates the quota to grant by subtracting the specified amount in bytes from the initial quota limit minus the quota used so far.
- **initial**—Calculates the quota to grant by subtracting the specified amount in bytes from the initial quota limit.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

quota-name

Name(s) of quota defined in the CMP database.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

mon-key

Name(s) of a monitoring key in the CMP database.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Allows quota profiles to be associated with one or more monitoring keys. This action can be used at the session and rule levels. If two policy actions grant usage for the same monitoring key or usage instance, the last action takes precedence, unless an action grants uplink volume followed by an action that grants downlink volume (or vice versa), which case the actions are grouped as one action when the message is processed. A policy that grants quota for a monitoring key will overwrite any previous grant of quota for that same monitoring key. This includes any subtraction previously enabled for the same monitoring key. See [Managing Quotas](#) for information on quotas. See [Managing Monitoring Keys](#) for information on monitoring keys. The best quota is determined using the following rules:

1. Passes are always better than plans
2. Between two passes, the one with the higher priority is better
3. Between two passes with equal priorities, the one with the earlier expiration date is better
4. Between two passes with equal priorities and expiration dates, the one with the earlier purchase date is better

Example 36-13 Example

```
where the request is creating a new session
grant total volume to 100 percent used for BEST OF Monthly1,Daily1
using key1

continue processing message
```

grant total volume to specified percent used for select quota

Mode

Wireless

Syntax

```
grant service-type to extended-percent percent quota-type for quota-name
```

Parameters***service-type***

One of the following:

- **time**
- **total volume**
- **uplink volume**
- **downlink volume**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

extended-percent

An extended, non-integer percentage that can exceed 100 (for example, 102.4%).



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

quota-type

One of the following:

- **used** (default)—Calculates the quota to grant by subtracting the specified amount in bytes from the initial quota limit minus the quota used so far.
- **initial**—Calculates the quota to grant by subtracting the specified amount in bytes from the initial quota limit.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

quota-name

Name(s) of quota defined in the CMP database.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Provisions the session quota limit in time or volume based on a percentage of the quota used, retrieved from the SPR, for the named quota profile. This action can only be used at the session level. See [Managing Quotas](#) for information on quotas.

Example 36-14 Example

```
where the request is creating a new session
grant total volume to 100 percent used for Monthly1,Daily1

continue processing message
```

grant total volume to specified percent used for select quota using monitoring key

Mode

Wireless

Syntax

```
grant service-type to extended-percent percent quota-type for quota-name
using mon-key
```

Parameters

service-type

One of the following:

- **time**
- **total volume**
- **uplink volume**
- **downlink volume**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

extended-percent

An extended, non-integer percentage that can exceed 100 (for example, 102.4%).



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

quota-type

One of the following:

- **used** (default)—Calculates the quota to grant by subtracting the specified amount in bytes from the initial quota limit minus the quota used so far.
- **initial**—Calculates the quota to grant by subtracting the specified amount in bytes from the initial quota limit.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

quota-name

Name(s) of quota defined in the CMP database.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

mon-key

Name(s) of a monitoring key in the CMP database.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Allows quota profiles to be associated with one or more monitoring keys. This action can be used at the session and rule levels. If two policy actions grant usage for the same monitoring key or usage instance, the last action takes precedence, unless an action grants uplink volume followed by an action that grants downlink volume (or vice versa), in which case the

actions are grouped as one action when the message is processed. A policy that grants quota for a monitoring key will overwrite any previous grant of quota for that same monitoring key. This includes any subtraction previously enabled for the same monitoring key. See [Managing Quotas](#) for information on quotas. See [Managing Monitoring Keys](#) for information on monitoring keys.

Example 36-15 Example

```
where the request is creating a new session
grant total volume to 100 percent used for Monthly1,Daily1 using key1

continue processing message
```

install PRA change for *PRA area(s)*

Mode

Wireless mode with the 3GPP mode enabled.

Syntax

```
install PRA change for PRA areas
```

Parameters

pra-areas

A single area or multiple specific PRA areas selected from the defined PRA areas, manually input, or Default.

- **CMP defined PRA lists**
Select one or more defined PRA lists
- **Manual Input**
Enter the identifier for the PRA in hexadecimal format or a custom PRA from a subscriber profile in the format *{User.CustomField}*. For information on creating custom fields in subscriber profiles, see the *CMP Wireless User's Guide*.

The manual input format for multiple PRAs is:

```
PRA
identifier1 [;PRA element list1],PRA identifier2 [; PRA element
list2],...
```

The format of PRA identifier and PRA Element List is according to section 8.108 of TS 29.274[9]. It is specified in Hexadecimal format. If only has a PRA identifier then the PRA area is a predefined PRA area. If both PRA identifier and PRA Element List exists then it is a UE-dedicated PRA Area. The manual input is typically used to input a temporally PRA area. The manual input can also be used to get a PRA area from Custom field of subscriber. For example, *{User.Custom4}*. If the operator wants to manually input a PRA area they need to get the Hexadecimal value for each. Different vendors/operators should interact or

exchange PRA info using the Hexadecimal representation as defined in section 8.108 of TS 29.274[9].

The manual input format for a single PRA is:

```
PRA identifier [, PRA element list]
```

- **Default**

The PRA to which the user equipment is already subscribed, if any.

The Default option specifies using the default PRA area. The default PRA is the PRA area subscribed or provisioned by the PCRF for the UE during IP-CAN session life cycle. It is either a UE- dedicated or predefined PRA area. It can be a PRA area that is retrieved from the subscriber profile (normally UE-dedicated) or a PRA area defined in the CMP (normally predefined). When used , this Default option means to check whether the UE has subscribed to a PRA area but does not care what the PRA area is.

 Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Install PRA change for specific PRA areas. For Single PRA make sure only the first PRA area is installed.

install *specified* ADC rule(s) for *select scope*

Mode

Wireless

Syntax

```
install adc-rule ADC rule(s) for adc-rule-scope-install
```

Parameters

adc-rule

Names of application detection control traffic profiles that are defined in the CMP database. The traffic profiles must be one of the following types:

- **ADC Rule**
- **Predefined ADC Rule**
- **Predefined ADC Rule Base**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

adc-rule-scope-install

One of the following:

- **session**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

The specified ADC rule or rules are installed for the session, using the values specified in the associated traffic profile. See [Managing Traffic Profiles](#) for information on traffic profiles.

Example 36-16 Example

```
where the enforcement session is a DPI enforcement session
install ADC1,ADC5,ADC6 ADC rule(s) for session
continue processing message
```

install specified ADC rule(s) for select scope active between start time and end time

Mode

Wireless

Syntax

```
install adc-rule ADC rule(s) for adc-rule-scope-install active between
start-and-end-time
```

Parameters***adc-rule***

Names of application detection control traffic profiles that are defined in the CMP database. The traffic profiles must be one of the following types:

- **ADC Rule**

- **Predefined ADC Rule**
- **Predefined ADC Rule Base**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

adc-rule-scope-install

One of the following:

- **session**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

start-and-end-time

Specifies the start and end time for rule to be active. If start time is not specified, the rule becomes active immediately. If end time is not specified, the rule never deactivates. Select either absolute time or relative time for both start-time and end-time:

- **None**— Specifies the time to start/end in the form *HH:mm:ss*. The date is calculated to be the minimum future date for that time.
- **Specific Time** — Specifies the time and date to start/end in the form *YYYY-MM-ddTHH:mm:ss*.
- **Relative time** — Specifies the number of hours, minutes, or seconds from the current time to start/end in the form *HH:mm:ss*. Variables include:
 - Hours
 - Minutes
 - Seconds
- **Policy Counter ID** — Select one or more policy counter IDs defined in the CMP database; or enter a comma-separated string of policy counter IDs.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

The specified ADC rule or rules are installed for the session, using the values specified in the associated traffic profile, and is active between the specified start and end times. See [Managing Traffic Profiles](#) for information on traffic profiles.

install *specified* ADC rule(s) for *select scope* active within *Time Period*

Mode

Wireless

Syntax

```
install adc-rule ADC rule(s) for adc-rule-scope-install active within  
time-period
```

Parameters***adc-rule***

Names of application detection control traffic profiles that are defined in the CMP database. The traffic profiles must be one of the following types:

- **ADC Rule**
- **Predefined ADC Rule**
- **Predefined ADC Rule Base**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

adc-rule-scope-install

One of the following:

- **session**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

time-period

Select a predefined time period.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

The specified ADC rule or rules are installed for the session, using the values specified in the associated traffic profile, and the rule is active for the specified time period. When a time period is used in a policy, you cannot delete that time period from the CMP database. See [Managing Traffic Profiles](#) for information on traffic profiles.

install *specified* ADC rule(s) for *select scope* for *specified* retry profile
active between *start time* and *end time*

Mode

Wireless

Syntax

```
install adc-rule ADC rule(s) for adc-rule-scope-install for retry-profile active  
between start-end-time
```

Parameters***adc-rule***

Names of application detection control traffic profiles that are defined in the CMP database. The traffic profiles must be one of the following types:

- **ADC Rule**
- **Predefined ADC Rule**
- **Predefined ADC Rule Base**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

adc-rule-scope-install

One of the following:

- **session**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

retry-profile

Name of a retry profile that is defined in the CMP database. (See [Managing Retry Profiles](#) for more information.)

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

start-end-time

Specifies the start and end time for rule to be active. If a start time is not specified, the rule becomes active immediately. If an end time is not specified, the rule never deactivates. Select either absolute time or relative time for both the start time and the end time:

- **Absolute time but no date** — Specifies the time to start/end in the form *HH:mm:ss*. The date is calculated to be the minimum future date for that time.
- **Absolute time and date** — Specifies the time and date to start/end in the form *YYYY-MM-ddTHH:mm:ss*.
- **Relative Time** — Specifies the number of hours, minutes, or seconds from the current time to start/end in the form *HH:mm:ss*. Variables include:
 - Hours
 - Minutes
 - Seconds

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

The specified ADC rule or rules are installed for the session, using the values specified in the associated traffic profile and the associated retry profile, and the rule is active for the specified time period. See [Managing Traffic Profiles](#) for information on traffic profiles.

install *specified* ADC rule(s) for *select scope* for *specified retry profile*
active within *Time Period*

Mode

Wireless

Syntax

```
install adc-rule ADC rule(s) for adc-rule-scope-install for retry-profile active  
within time-period
```

Parameters

adc-rule

Names of application detection control traffic profiles that are defined in the CMP database. The traffic profiles must be one of the following types:

- **ADC Rule**
- **Predefined ADC Rule**
- **Predefined ADC Rule Base**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

adc-rule-scope-install

One of the following:

- **session**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

retry-profile

Name of a retry profile that is defined in the CMP database. (See [Managing Retry Profiles](#) for more information.)

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

time-period

Specifies the time period when the rule is active. When that time period begins the rule activates, and when the time period ends the rule deactivates. Select one of the following:

- **Time Period** — Select pre-defined time period.
- **Policy Table Field** — Select time-related field from Policy Table selected for this Policy.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

The specified ADC rule or rules are installed for the session, using the values specified in the associated traffic profile and the associated retry profile, and the rule is active for the specified time period. See [Managing Traffic Profiles](#) for information on traffic profiles.

install *specified* ADC rule(s) for *select scope* with *specified retry profile*

Mode

Wireless

Syntax

```
install adc-rule ADC rule(s) for adc-rule-scope-install with retry-profile
```

Parameters***adc-rule***

Names of application detection control traffic profiles that are defined in the CMP database. The traffic profiles must be one of the following types:

- **ADC Rule**
- **Predefined ADC Rule**
- **Predefined ADC Rule Base**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

adc-rule-scope-install

One of the following:

- **session**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

retry-profile

Name of a retry profile that is defined in the CMP database. (See [Managing Retry Profiles](#) for more information.)

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

The specified ADC rule or rules are installed for the session, using the values specified in the associated traffic profile and the associated retry profile. See [Managing Traffic Profiles](#) for information on traffic profiles.

install *specified* PCC rule(s) for *select scope*

Mode

Wireless

Syntax

```
install pcc-rule PCC rule(s) for pcc-rule-scope-install
```

Parameters

pcc-rule

Names of policy and charging control traffic profiles that are defined in the CMP database. The PCC profiles must be one of the following types:

- **PCC Rule**
- **Predefined PCC Rule**
- **Predefined PCC Rule Base**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

pcc-rule-scope-install

One of the following:

- **flow**
- **session**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

The specified PCC rule or rules are installed for either the session or flow, using the values specified in the associated traffic profile. See [Managing Traffic Profiles](#) for information on traffic profiles.

install specified PCC rule(s) for select scope active between start time and end time

Mode

Wireless

Syntax

`install pcc-rule PCC rule(s) for pcc-rule-scope-install active between start-and-end-time`

Parameters

pcc-rule

Names of policy and charging control traffic profiles that are defined in the CMP database. The traffic profiles must be one of the following types:

- **PCC Rule**
- **Predefined PCC Rule**
- **Predefined PCC Rule Base**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

pcc-rule-scope-install

One of the following:

- **flow**
- **session**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

start-and-end-time

Specifies the start and end time for rule to be active. If start time is not specified, the rule becomes active immediately. If end time is not specified, the rule never deactivates. Select either absolute time or relative time for both start-time and end-time:

- **None** — Specifies the time to start/end in the form *HH:mm:ss*. The date is calculated to be the minimum future date for that time.
- **Specific Time** — Specifies now or the date and time to start/end. Variables include:
 - Date — Pick the date from the calendar interface
 - Time
 - UTC Offset — Select number of hours before or after UTC time to start/end
 - now — Select to start/end now
 - time only — Select to use the time only

The content can use policy variable substitution.

- **Relative time** — Specifies the number of hours, minutes, or seconds from the current time to start/end in the form HH:mm:ss. Variables include:
 - Hours
 - Minutes
 - Seconds
- **Policy Counter Id** — Select one or more policy counter IDs defined in the CMP database; or enter a comma-separated string of policy counter IDs.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

The specified PCC rule or rules are installed for either the session or flow, using the values specified in the associated traffic profile, and is active between the specified start and end times. See [Managing Traffic Profiles](#) for information on traffic profiles.

install *specified* PCC rule(s) for *select scope* active within *Time Period*

Mode

Wireless

Syntax

```
install pcc-rule PCC rule(s) for pcc-rule-scope-install active within  
time-period
```

Parameters***pcc-rule***

Names of policy and charging control profiles that are defined in the CMP database. The traffic profiles must be one of the following types:

- **PCC Rule**
- **Predefined PCC Rule**
- **Predefined PCC Rule Base**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

pcc-rule-scope-install

One of the following:

- **flow**
- **session**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

time-period

Specifies the time period when the rule is active. When that time period begins the rule activates, and when the time period ends the rule deactivates. Select one of the following:

- **Time Period** — Select pre-defined time period.
- **Policy Table Field** — Select time-related field from Policy Table selected for this Policy.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

The specified PCC rule or rules are installed for either the session or flow, using the values specified in the associated traffic profile, and the rule is active for the specified time period. When a time period is used in a policy, you cannot delete that time period from the CMP database. See [Managing Traffic Profiles](#) for information on traffic profiles.

*install specified PCC rule(s) for select scope for specified retry profile
active between start time and end time*

Mode

Wireless

Syntax

`install pcc-rule PCC rule(s) for pcc-rule-scope-install for retry-profile active
between start-end-time`

Parameters

pcc-rule

Names of policy and charging control traffic profiles that are defined in the CMP database. The traffic profiles must be one of the following types:

- **PCC Rule**
- **Predefined PCC Rule**
- **Predefined PCC Rule Base**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

pcc-rule-scope-install

One of the following:

- **flow**
- **session**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

retry-profile

Name of a retry profile that is defined in the CMP database. (See [Managing Retry Profiles](#) for more information.)



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

start-and-end-time

Specifies the start and end time for rule to be active. If start time is not specified, the rule becomes active immediately. If end time is not specified, the rule never deactivates. Select either absolute time or relative time for both start-time and end-time:

- **None**— Specifies the time to start/end in the form *HH:mm:ss*. The date is calculated to be the minimum future date for that time.
- **Specific Time** — Specifies now or the date and time to start/end. Variables include:
 - Date — Pick the date from the calendar interface.
 - Time
 - UTC Offset — Select number of hours before or after UTC time to start/end.
 - now — Select to start now.
 - time only — Select to use the time only.

The content can use policy variable substitution.
- **Relative Time** — Specifies the number of hours, minutes, or seconds from the current time to start/end in the form *HH:mm:ss*. Variables include:
 - Hours
 - Minutes
 - Seconds
- **Policy Counter Id** — Select one or more policy counter IDs defined in the CMP database; or enter a comma-separated string of policy counter IDs.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

The specified PCC rule or rules are installed for either the session or flow, using the values specified in the associated traffic profile and the associated retry profile, and is active between the specified start and end times. See [Managing Traffic Profiles](#) for information on traffic profiles.

install specified PCC rule(s) for select scope for specified retry profile active within Time Period

Mode

Wireless

Syntax

```
install pcc-rule PCC rule(s) for pcc-rule-scope-install for retry-profile active
within time-period
```

Parameters

pcc-rule

Names of policy and charging control traffic profiles that are defined in the CMP database. The traffic profiles must be one of the following types:

- **PCC Rule**
- **Predefined PCC Rule**
- **Predefined PCC Rule Base**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

pcc-rule-scope-install

One of the following:

- **flow**
- **session**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

retry-profile

Name of a retry profile that is defined in the CMP database. (See [Managing Retry Profiles](#) for more information.)



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

time-period

Specifies the time period when the rule is active. When that time period begins the rule activates, and when the time period ends the rule deactivates. Select one of the following:

- **Time Period** — Select pre-defined time period.

- **Policy Table Field** — Select time-related field from policy table selected for this policy.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

The specified PCC rule or rules are installed for either the session or flow, using the values specified in the associated traffic profile and the associated retry profile, and the rule is active for the specified time period. See [Managing Traffic Profiles](#) for information on traffic profiles.

install specified PCC rule(s) for select scope with specified retry profile

Mode

Wireless

Syntax

```
install pcc-rule PCC rule(s) for pcc-rule-scope-install with retry-profile
```

Parameters***pcc-rule***

Names of policy and charging control traffic profiles that are defined in the CMP database. The traffic profiles must be one of the following types:

- **PCC Rule**
- **Predefined PCC Rule**
- **Predefined PCC Rule Base**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

pcc-rule-scope-install

One of the following:

- **flow**
- **session**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

retry-profile

Name of a retry profile that is defined in the CMP database. (See [Managing Retry Profiles](#) for more information.)

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

The specified PCC rule or rules are installed for either the session or flow, using the values specified in the associated traffic profile and the associated retry profile. See [Managing Traffic Profiles](#) for information on traffic profiles.

mark request AVP *name* as failed if exists and send *always*

Mode

Wireless

Syntax

mark request AVP *name* as failed if exists and send *send-mode*

Parameters***name***

String representing existing AVP name, entered in the format *AVPname:VendorID* or, for nested AVP names in an AVP group, entered in the format *[AVPname1]:VendorID. [AVPname2]:VendorID ...* for the members of the grouped AVPs. There is also the option to evaluate as an expression (click to select check box).

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

send-mode

One of the following:

- **always** (default)
- **unless rejected**
- **if rejected**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Marks a request AVP as failed in the reply message, and notifies the opposite peer of the failed AVP validation. This action supports both loaded base Diameter AVPs and third-party AVPs.

overwrite Conditional Policy Information with Execution-Time to *time* and parameters *specified*

Mode

Wireless

Syntax

replace-add Conditional Policy Information with Execution-Time to *time-type* and parameters *AVP-values*

Parameters***replace-add***

One of the following:

- **overwrite** (default)— Replace any existing Conditional-Policy-Information AVPs
- **add**— Create a new Conditional-Policy-Information AVP and add or append it to the existing list

time-type

Opens a window that prompts you to specify the execution time with a variety of options. The options available depend on what you select for **Set Time**:

- **Specific Time**— Specifies execution at a specific time. The available options are:
 - **Enter now or a datetime**— Enter the time:

- * **now** (default)—The local date and time.
- * A date and time in the format: `yyyy-mm-ddThh:mm:ss+UTCOffset`.



Note:

Enter the date-time directly into the field or click the calendar icon for assistance:

- * **Date**— Select the date from the calendar interface.
 - * **Time**— Select hh:mm:ss.
 - * **UTC Offset**— Select number of hours before or after UTC time to start.
 - * **now**— Select for the local date-time.
 - * **time only**— Select to use the time only.
- * A policy variable.
 - * A JavaScript code snippet— Enter a JavaScript statement that evaluates to a date-time in the format: `yyyy-mm-ddThh:mm:ss+UTCOffset`. Click **Evaluate as expression** to bypass date-time format validation.
- **Select Time Mode**— The optional time zone. Select one of the following:
 - * **N/A**
 - * **CONFIGURED LOCAL TIME**— Calculate the time from the location configured for this MPE device
 - * **SYSTEM LOCAL TIME**— Calculate the time from the location of this MPE device
 - * **USER LOCAL TIME** (default)— Calculate the time from the location configured for the user equipment's location
 - **Relative Time**— Specifies the number of hours, minutes, or seconds from the current time to the execution time. Select the time unit (**Hours**, **Minutes**, or **Seconds**) and enter a positive integer. For example, select **Hours** and enter `12` to set the execution time to 12 hours from now. You can instead enter a policy rule variable.
 - **Policy Counter Id**— Select one or more policy counter IDs defined in the CMP database; or enter a comma-separated string of policy counter IDs.
 - **Day Of Week**— Specifies one or more days of the week, plus a time during the day:
 - **Choose the day(s) of the week to check:**
 - * **Sunday**
 - * **Monday**
 - * **Tuesday**

- * **Wednesday**
- * **Thursday**
- * **Friday**
- * **Saturday**
- **Enter time:** The execution time during the day, in the form *hh:mm*.
- **Select Time Mode**— The optional time zone. Select one of the following:
 - * **N/A**
 - * **CONFIGURED LOCAL TIME**— Calculate the time from the location configured for this MPE device
 - * **SYSTEM LOCAL TIME**— Calculate the time from the location of this MPE device
 - * **USER LOCAL TIME** (default)— Calculate the time from the location configured for the user equipment's location



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

AVP-values

Enter values for:

- Diameter-APN-Aggregate-Max-Bitrate-UL Refer to [QoS Values for Policy Conditions and Actions](#) for QoS information.



Note:

This value cannot be greater than 4294967295000.

- Diameter-APN-Aggregate-Max-Bitrate-DL Refer to [QoS Values for Policy Conditions and Actions](#) for QoS information.



Note:

This value cannot be greater than 4294967295000.

- Diameter Default EPS Bearer QoS, which include:
 - Diameter Default EPS Bearer QCI
 - Diameter Default EPS Bearer ARP Priority Level

- Diameter Default EPS Bearer ARP Preemption Capability:
 - * N/A
 - * PREEMPTION_CAPABILITY_ENABLED
 - * PREEMPTION_CAPABILITY_DISABLED
- Diameter Default EPS Bearer ARP Preemption Vulnerability:
 - * N/A
 - * PREEMPTION_VULNERABILITY_ENABLED
 - * PREEMPTION_VULNERABILITY_DISABLED

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

You can use this action in two ways. You can add a new Conditional-Policy-Information AVP with specified parameter values to the existing list of Conditional-Policy-Information AVP(s). Alternatively, you can replace an existing list of Conditional-Policy-Information AVP(s).

Example 36-17 Example

The following example shows adds Conditional-Policy-information AVPs and overwrite the Conditional-Policy-information AVPs:

```
where the request is modifying an existing session
And where the event trigger is one of OUT_OF_CREDIT
add Conditional Policy Information with Execution-Time to
2016-11-11T00:00:00 and parameters
Diameter APN-Aggregate-Max-Bitrate-DL 1000
add Conditional Policy Information with Execution-Time to
2016-11-12T00:00:00 and parameters
Diameter APN-Aggregate-Max-Bitrate-DL 1500
overwrite Conditional Policy Information with Execution-Time to
2016-11-13T00:00:00 and parameters
Diameter APN-Aggregate-Max-Bitrate-DL 2000
```

overwrite DSCP/TOS field with #**Mode**

Cable

Syntax

overwrite DSCP/TOS field with *dscp*

Parameters

dscp

A numeric representation of DSCP bits to be inserted into the message.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Overwrites the DSCP/TOS field with a value. Although this is a number, the policy wizard includes a customized dialog to help you construct the value.

overwrite SessionClassId with

Mode

Cable

Syntax

overwrite SessionClassId with *number*

Parameters

number

A numeric value.

Valid range is 0–2000000000.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Overwrites the *SessionClassId* field in the message with the specified value.

re-authorize all credit control sessions associated with User

Mode

Wireless

Syntax

re-authorize all credit control sessions associated with User

Parameters

None

Description

Triggers reauthorization for PCEF sessions for all the user's sessions.

re-authorize all PCEF/TDF sessions associated with *select scope*

Mode

Wireless

Syntax

re-authorize all PCEF/TDF sessions associated with *pcef-scope-install*

Parameters

pcef-scope-install

One of the following:

- **IP-CAN session**
- **user**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers reauthorization for PCEF or TDF sessions, either within the IP-CAN session associations (that is, all Gx sessions sharing the same IP address and APN) or for all the user's sessions (that is, all Gx sessions sharing the same user ID). Each reauthorization request contains the original event that triggered the reauthorization action, so information from this event can be evaluated by the Policy Engine during the evaluation of the request. For example, an event trigger received in a CCR on one interface, such as RAT_CHANGE, can be used in the evaluation of the reauthorization request triggered by this CCR. This action is valid regardless of whether Gx correlation is enabled or disabled.

release all credit control sessions associated with User

Mode

Wireless

Syntax

```
release all credit control sessions associated with User
```

Parameters

None

Description

Triggers release of credit control sessions for all the sessions for the user.

release all PCEF/TDF sessions associated with *select scope*

Mode

Wireless

Syntax

```
release all PCEF/TDF sessions associated with pcef-scope-install
```

Parameters

pcef-scope-install

One of the following:

- **IP-CAN session**
- **user**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Triggers release of PCEF or TDF sessions, either within the IP-CAN session associations (that is, all Gx sessions sharing the same IP address and APN) or for all the user's sessions (that is, all Gx sessions sharing the same user ID).

release the session

Mode

Wireless

Syntax

```
release the session
```

Parameters

None

Description

Releases the session.

release the session with cause *'ReleaseCause'*

Mode

Wireless

Syntax

```
release the session with cause release_cause
```

Parameters

release_cause

One of the following:

- **UNSPECIFIED_REASON**
- **UE_SUBSCRIPTION_REASON**
- **INSUFFICIENT_SERVER_RESOURCES**
- **IP_CAN_SESSION_TERMINATION**
- **UE_IP_ADDRESS_RELEASE** — Indicates the IPv4 address of a dual-stack IP-CAN session is released (applies only to Sd interface)

Description

Releases the session and provides the cause.

remove ADC rule type(s) *select types of rules for select scope*

Mode

Wireless

Syntax

```
remove ADC rule types adc-rule-type for adc-rule-scope-install
```

Parameters

adc-rule-type

One or more of the following:

- **none**
- **predefined**
- **predefined base**
- **dynamically provisioned**
- **all**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

adc-rule-scope-install

One of the following:

- **session**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Removes the application detection control rules from the current session based on their type. See [Managing Traffic Profiles](#) for information on ADC traffic profiles.

remove all policy context properties

Mode

Cable, Wireless, Wireline

Syntax

```
remove all policy context properties
```

Parameters

None

Description

In Wireless mode, removes all subscriber properties in the SPR.

In Cable mode, removes all policy context properties.

In Wireline mode, removes all policy context properties.

Removes all policy context properties.

remove all the *scope* state variables and save *always*

Mode

Wireless

Syntax

```
remove all the scope state variables and save save-mode
```

Parameters***scope***

One of the following:

- **subscriber**—Subscribers in the remote SPR.
- **pool**—Subscriber pool defined in the SPR.
- **subscriber_local**—Subscribers in the local MPE.
- **session**—Session variables that have a value as long as the session they are associated with is open.
- **policy_evaluation**—Policy evaluation variables that last only for the duration of the policy evaluation cycle.

**Note:**

save-mode is not applicable with the **policy_evaluation** scope since this variable only exists in the policy.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

save-mode

One of the following:

- **always** (default)

- **unless rejected**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Deletes all the state variable for a scope. You can specify that the properties are not deleted if the policy rejects the message.

remove Conditional Policy Information(s)

Mode

Wireless

Syntax

```
remove Conditional Policy Information(s)
```

Parameters

None

Description

Deletes all Conditional-Policy-Information for the session and sets the authorized APN-AMBR-UL/DL values and DEBQ values (if DIAMETER.GX.RemoveCPINewApnAndDebgControl is set true).

remove custom AVP *name* from reply *always*

Mode

Wireless

Syntax

```
remove custom AVP name from reply send-mode
```

Parameters***name***

An existing AVP name and Vender ID, or an AVP name from an existing Policy Table.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

send-mode

One of the following:

- **always** (default)
- **unless rejected**
- **if rejected**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Removes the custom AVP name previously set from the reply message.

remove *default* PCC rules of *default* TDF application IDs for APPLICATION_STOP

Mode

Wireless

Syntax

remove *traffic-profile* PCC rule(s) of *value-list* TDF application ID(s) for APPLICATION_STOP

Parameters

traffic-profile

One or more traffic profiles. For more information on traffic profiles, see [Managing Traffic Profiles](#).

If **default** (default) is specified, all associated PCC rules according to Application-Detection-Information AVP in this report are removed. If specific PCC rules are specified, the associated PCC rules that should be removed must also in specified PCC rules.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

value-list

A comma-delimited list of values to compare against.

If **default** (default) is specified, all PCC rules according to Application-Detection-Information AVP in this report are removed. If specific TDF-Application-Identifiers are specified, the associated PCC rules that should be removed must also in specified PCC rules.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

This action removes PCC rules when the PCEF reports an application stop.

The TDF-Application-Identifier and TDF-Application-Instance-Identifier must be bound to the PCC rules before the application start.

If there is not a TDF-Application-Instance-Identifier in the Application-Detection-Information AVP, but PCC rules contain binding info to that a TDF-Application-Identifier is installed, the MPE device logs the following warning in the trace log and continues with the session processing.

```
Policy Trace policy name: Could not execute 'remove PCC rules of TDF
application
ids for APPLICATION_STOP' because there is no TDF-Application-Instance-
Identifier in
Application-Detection-Information AVP
```

If the PCC rules that are associated with the TDF-Application-Identifier and TDF-Application-Instance-Identifier info is not found, then MPE device logs the following warning in the trace log and continues with the session processing.

```
Policy Trace policy name: Could not execute 'remove PCC rules of TDF
application
ids for APPLICATION_STOP ' because can not find related PCC rule to remove,
TDF-Application-Identifier:TDFID,
TDF-Application-Instance-Identifier:InstanceID
```

remove PCC rule for the flow

Mode

Wireless

Syntax

```
remove PCC rule for the flow
```

Parameters

None

Description

Removes the policy and charging control rule from the current flow. See [Managing Traffic Profiles](#) for information on PCC traffic profiles.

remove PCC rule type(s) *select types of rules for select scope*

Mode

Wireless

Syntax

```
remove PCC rule types pcc-rule-type for pcc-rule-scope-install
```

Parameters

pcc-rule-type

One or more of the following:

- **none**
- **predefined**
- **predefined base**
- **dynamically provisioned**
- **all**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

pcc-rule-scope-install

One of the following:

- **flow**
- **session**
- **all**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Removes the policy and charging control rules from the current flow/session based on their type. See [Managing Traffic Profiles](#) for information on PCC traffic profiles.

remove policy context property *name*

Mode

Cable, Wireless, Wireline

Syntax

```
remove policy context property property-name
```

Parameters***property-name***

String. May contain policy rule variables (see [Policy Rule Variables](#)) to perform parameter substitution within the property name.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Removes a policy context property (in Cable mode and Wireline mode) or a subscriber property in the SPR (in Wireless mode).

remove PRA change for *PRA area(s)*

Mode

Wireless mode with the 3GPP mode enabled.

Syntax

remove PRA change for PRA areas

Parameters

pra-areas

A single area or multiple specific PRA areas selected from the defined PRA areas, manually input, or Default.

- **CMP defined PRA lists**

Select one or more defined PRA lists

- **Manual Input**

Enter the identifier for the PRA in hexadecimal format or a custom PRA from a subscriber profile in the format *{User.CustomField}*. For information on creating custom fields in subscriber profiles, see the *CMP Wireless User's Guide*.

The manual input format for multiple PRAs is:

```
PRA
identifier1 [;PRA element list1],PRA identifier2 [; PRA element
list2],...
```

The format of PRA identifier and PRA Element List is according to section 8.108 of TS 29.274[9]. It is specified in Hexadecimal format. If only has a PRA identifier then the PRA area is a predefined PRA area. If both PRA identifier and PRA Element List exists then it is a UE-dedicated PRA Area. The manual input is typically used to input a temporally PRA area. The manual input can also be used to get a PRA area from Custom field of subscriber. For example, {User.Custom4}. If the operator wants to manually input a PRA area they need to get the Hexadecimal value for each. Different vendors/operators should interact or exchange PRA info using the Hexadecimal representation as defined in section 8.108 of TS 29.274[9].

The manual input format for a single PRA is:

```
PRA identifier [, PRA element list]
```

- **Default**

The PRA to which the user equipment is already subscribed, if any.

The Default option specifies using the default PRA area. The default PRA is the PRA area subscribed or provisioned by the PCRF for the UE during IP-CAN session life cycle. It is either a UE- dedicated or predefined PRA area. It can be a PRA area that is retrieved from the subscriber profile (normally UE-dedicated) or a PRA area defined in the CMP (normally predefined). When used , this Default option means to check whether the UE has subscribed to a PRA area but does not care what the PRA area is.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Remove the PRA change for specific PRA areas, this is only for multiple PRA.

remove *specified* ADC rule(s)

Mode

Wireless

Syntax

```
remove adc-rule ADC rules
```

Parameters***adc-rule***

Names of application detection control traffic profiles that are defined in the CMP database. The traffic profiles must be one of the following types:

- **ADC Rule**
- **Predefined ADC Rule**
- **Predefined ADC Rule Base**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Removes the ADC rules from the current session.

remove *specified* PCC rule(s)

Mode

Wireless

Syntax

```
remove pcc-rule PCC rules
```


Parameters

pcc-rule

Names of policy and charging control traffic profiles that are defined in the CMP database. The traffic profiles must be one of the following types:

- **PCC Rule**
- **Predefined PCC Rule**
- **Predefined PCC Rule Base**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Removes the PCC rules from the current flow/session. See [Managing Traffic Profiles](#) for information on traffic profiles.

remove the *scope* state variable *name* and save *always*

Mode

Wireless

Syntax

```
remove the scope state variable variable-name and save save-mode
```

Parameters

scope

One of the following:

- **subscriber**—Subscribers in the remote SPR.
- **pool**—Subscriber pool defined in the SPR.
- **subscriber_local**—Subscribers in the local MPE.
- **session**—Session variables that have a value as long as the session they are associated with is open.
- **policy_evaluation**—Policy evaluation variables that last only for the duration of the policy evaluation cycle.



Note:

save-mode is not applicable with the **policy_evaluation** scope since this variable only exists in the policy.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

variable-name

String.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

save-mode

One of the following:

- **always** (default)
- **unless rejected**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Deletes a state variable. You can specify that the variable is not deleted if the policy rejects the message.

request usage report for *monitoring key*

Mode

Wireless

Syntax

request usage report for *mon-key*

Parameters

mon-key

Name(s) of a monitoring key in the CMP database.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Requests a usage report from the PCEF. This sets the value of the Usage-Monitoring-Information AVP sent to the MPE device to USAGE_MONITORING_REPORT_REQUIRED. See [Managing Monitoring Keys](#) for information on monitoring keys.

reset all plan usage

Mode

Wireless

Syntax

reset all plan usage

Parameters

None

Description

Resets all plans for the subscriber.

reset all plan usage with reset type of *select reset type*

Mode

Wireless

Syntax

reset all plan usage with reset type of *reset_type*

Parameters

reset_type

One of the following:

- **Usage**
- **Rollover**
- **Billing Cycle**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Resets all plan usage for the selected reset type. See [Managing Quotas](#) for information on quotas.

reset all subscriber data

Mode

Wireless

Syntax

```
reset all subscriber data
```

Parameters

None

Description

Resets all data for the subscriber.

reset select quota reset type of select reset type

Mode

Wireless

Syntax

```
reset quota-name reset type of reset-type
```

Parameters

quota-name

Name(s) of quota defined in the CMP database.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

reset-type

One of the following:

- **Usage**
- **Rollover**
- **Billing Cycle**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Resets the selected quota with the selected reset type. See [Managing Quotas](#) for information on quotas.

reset the last delivery time of *specific use case(s)* in the user state variable of LastDeliveryTime

Mode

Wireless mode with SMPP enabled

Wireless-C mode with CMPP enabled.

Syntax

reset the last delivery time of *use_case_names* in the user state variable of LastDeliveryTime

Parameters

use_case_names

One or more use case names separated by commas.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Resets the last delivery time of the specified use cases in the subscriber state field of *LastDeliveryTime*.

Example 36-18 Example

```
where the request is creating a new session
  And where the enforcement session is an IP-CAN session
  And where the subscriber state variable usrStatus exists
  And where the subscriber state variable usrStatus matches one of `1`
  And where the last delivery time of usecase1 exists in the user state
variable of LastDeliveryTime
reset the last delivery time of usecase1 in the user state variable of
LastDeliveryTime
continue processing message
```

reset usage for *select quota*

Mode

Wireless

Syntax

```
reset usage for quota-name
```

Parameters***quota-name***

Name(s) of quota defined in the CMP database.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Resets the selected quota. See [Managing Quotas](#) for information on quotas.

revalidate the session at *datetime* using *configured local time*

Mode

Wireless

Syntax

revalidate the session at *datetime* using *time-zone*

Parameters

datetime

One of the following:

- A policy variable.
- **now** (default)—The local date-time.
- A date-time in the format: *yyyy-mm-ddThh:mm:ss+UTCOffset*.

Note:

Enter the date-time directly into the field or click the calendar icon for assistance:

- **Date**—Select the date from the calendar interface.
- **Time**—Select hh:mm:ss.
- **UTC Offset**—Select number of hours before or after UTC time to start.
- **now**—Select for the local date-time.
- **Time only**—Select to use the time only.

- A JavaScript code snippet—Enter a JavaScript statement that evaluates to a date-time in the format: *yyyy-mm-ddThh:mm:ss+UTCOffset*. Click **Evaluate as expression** to bypass date-time format validation.

Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

time-zone

One of the following:

- **CONFIGURED LOCAL TIME** (default)—Calculate the time from the location configured for this MPE device

- **SYSTEM LOCAL TIME**—Calculate the time from the location of this MPE device
- **USER LOCAL TIME**—Calculate the time from the location configured for the user equipment's location

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Revalidates the session at the specified time. If time-zone information is available from the user equipment, time can be calculated from either the MPE device or the user equipment's location.

Example 36-19 Example

```
revalidate the session at {User.State.end-time} using configured local time
```

schedule next RAR for resetting usage for *select quota*

Mode

Wireless

Syntax

```
schedule next RAR for resetting usage for quota-name
```

Parameters***quota-name***

Name(s) of quota defined in the CMP database.

Description

Causes the next RAR that is sent to reset usage for a selected quota.

send CoA with *COA Template*

Mode

Wireless

Syntax

```
send CoA with coa
```


Parameters

coa

Select a RADIUS CoA template from the list.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Send a RADIUS change of authorization (CoA) message, constructed using the specified CoA template, to the broadband network gateway that sent the RADIUS request that caused the policy to be triggered. To send multiple CoA messages, include this action multiple times in the policy.

Example 36-20 Example

The following example issues an updated RADIUS CoA message when a Profile Notification Request (PNR) message is received from an SPR system:

```
where notification from Sh datasource is received for Quota Usage
send CoA with CoA10-24
continue processing message
```

send http *POST* notification to *select notification destination* with
headers *headers* and content *content*

Mode

Wireless mode or Cable mode with the SMS:SMPP or SMS:XML function enabled.

Syntax

```
send http http_method notification to server with headers headers and  
content content
```

Parameters

http_method

String. The HTTP method for the request message. Supported methods are:

- **POST**—(default) a method for sending data for processing by the application specified by URL
- **GET**—a method for requesting the retrieval of data located at the specified URL
- **PUT**—a method for requesting the storage of the data at the specified URL

- **DELETE**—a method for deleting the data located at the specified URL

server

A list of the defined notification servers. Select the notification server from the list. See [Managing Notification Servers](#) for information about adding a notification server.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

headers

String. One or more HTTP message headers (up to a maximum of 20 headers) using the format: *field-name:field-value*. For example, *Content-Type:text/xml*, *Content-Type:application/json*, and *Content-Type:text/plain*. See the HTTP standard at <http://www.ietf.org> for details on valid message header fields and values. This field cannot be empty.

**Note:**

MPE does not validate whether the field-value corresponds to the field-name.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

content

String. The message body content that supports any type of notification like JSON/XML/Text message. The content can use policy variable substitution and can contain up to 4000 characters.

**Note:**

MPE does not validate whether the message headers correspond to particular content.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Enables PCRF to send a configurable HTTP request message using the Web services interface. These notification messages are sent to pre-configured destinations. After a notification message is sent, PCRF receives the response from the specified URL. In the event of a failure, PCRF does not attempt to re-send the message.

Example 36-21 Examples**XML POST**

```
send http POST notification to NS1 with headers
Content-Type:text/xml;charset=UTF-8 and content <?xml version="1.0"
encoding="UTF-8"?> <subscriber> <msisdn>{User.MSISDN}</msisdn>
<quota>{User.Quota.Foo.Volume}</quota> </subscriber>
```

JSON POST

```
send http POST notification to NS2 with
headers Content-Type: application/json and content
{"class":"Subscriber","entitlement":"Extended
Service`,`msisdn`: `{User.MSISDN}`, `name`: `{User.name}`}`
```

HTTP GET with query parameters

```
send http GET notification to
NS3 with headers Content-Type:text/plain and content ``
```

send http *POST* notification to url *URL* with headers *headers* and content *content*

Mode

Wireless mode or Cable mode with the SMS:SMPP or SMS:XML function enabled.

Syntax

```
send http http_method notification to url URL with headers headers and
content content
```

Parameters***http_method***

String. The HTTP method for the request message. Supported methods are:

- **POST**—(default) a method for sending data for processing by the application specified by URL
- **GET**—a method for requesting the retrieval of data located at the specified URL
- **PUT**—a method for requesting the storage of the data at the specified URL
- **DELETE**—a method for deleting the data located at the specified URL

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

URL

String. The dynamic URL for the server that is the destination for the HTTP request message. This URL can use policy variable substitution, for example, *http://10.15.20.190:80/rs/quota/notify/{User.MSISDN}*.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

headers

(Required) String. One or more HTTP message headers (up to a maximum of 20 headers) using the format: *field-name :field-value*. For example:

- Content-Type:text/xml
- Content-Type:application/json
- Content-Type:text/plain

See the HTTP standard at <http://www.ietf.org> for details on valid message header fields and values. This field cannot be empty.

**Note:**

MPE does not validate whether the field-value corresponds to the field-name.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

content

String. The message body content that supports any type of notification like JSON/XML/Text message. The content can use policy variable substitution and can contain a maximum of 4000 characters.



Note:

MPE does not validate whether the message headers correspond to particular content.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Enables PCRF to send a configurable HTTP request message using the web services interface. These notification messages are sent to either servers configured in CMP or to servers using a dynamic URL. After a notification message is sent, PCRF receives the response from the specified URL. In the event of a failure, PCRF does not attempt to resend the message.

Example 36-22 Examples

XML POST

```
send http POST notification to url
http://10.15.20.190:80/rs/quota/xmlnotify with
headers Content-Type:text/xml;charset=UTF-8 and
content <?xml version="1.0" encoding="UTF-8"?> <subscriber>
<msisdn>{User.MSISDN}</msisdn> <quota>{User.Quota.Foo.Volume}</quota>
</subscriber>
```

JSON POST

```
send http POST notification to url http://10.15.20.190:80/rs/quota/
jsonnotify/{User.MSISDN} with
headers Content-Type: application/json and content
{"class":"Subscriber","entitlement":"Extended
Service`,`msisdn`: `{User.MSISDN}`, `name`: `{User.name}`}`
```

HTTP GET with query parameters

```
send http GET notification to url
http://10.15.20.190:80/rs/quota/notify?
```

```
msisdn={User.MSISDN}&quota={User.Quota.Foo.Volume} with  
headers Content-Type:text/plain and content ``
```

send notification to syslog with *`message text`* and severity *`severity level`*

Mode

- Cable mode
- Wireless mode
- Wireless-C mode with CMPP enabled
- Wireline mode

Syntax

send notification to syslog with *`message`* and severity *`level`*

Parameters

message

String. This text may contain policy parameters (described later in this section) to perform parameter substitution within the message text. If you select **Evaluate as expression**, the text in the field is evaluated as an arithmetic expression, and the result is used.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

level

The sevlog severity. One of the following:

- **Emergency**
- **Alert**
- **Critical**
- **Error**
- **Warning**
- **Notice**
- **Info**
- **Debug**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Sends a message to the syslog service containing the specified message text and at the specified severity level.



Note:

Policies written before V7.5 that used the action `send alert` with ``text`` and severity ``severity level`` will be converted to use this action, which sends a notification to the syslog instead of an alarm to the CMP system.

send notification to trace log with ``message text`` and severity ``severity level``

Mode

- Cable mode
- Wireless mode
- Wireless-C mode with CMPP enabled
- Wireline mode

Syntax

send notification to trace log with ``message`` and severity ``level``

Parameters

message

String. This text may contain policy parameters (described later in this section) to perform parameter substitution within the message text. If you select **Evaluate as expression**, the text in the field is evaluated as an arithmetic expression, and the result is used.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

level

One of the following:

- **Emergency** (ID 4560)
- **Alert** (ID 4561)
- **Critical** (ID 4562)
- **Error** (ID 4563)
- **Warning** (ID 4564)
- **Notice** (ID 4565)
- **Info** (ID 4566)
- **Debug** (ID 4567)

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Sends a message to the trace log containing the specified message text and at the specified severity level. If the configured minimum notification severity level is higher than that specified in the policy action, then the policy action does not generate the notification.

**Note:**

Policies written before V7.5 that used the action `write `text`` to the log file are converted to use this action, with the severity of Info.

Example 36-23 Example

```
where the request is terminating an existing session
And where the enforcement session is an IP-CAN session
send notification to trace log with `### Alert :: Gx Session Terminated ###`
and severity `Alert`
continue processing message
```

send SMS Alert *`specified`* to user

Mode

Wireless mode with the SMS:XML function enabled.

Syntax

```
send SMS Alert `message` to user
```


Parameters

message

String. This text may contain policy parameters (described later in this section) to perform parameter substitution within the message text.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Sends an SMS alert message, with specified text, to the subscriber associated with the message.

Example 36-24 Example

```
send SMS alert `you have reached 80%% of your quota {User.MSISDN}` to
user
```

send SMS *specified* to *default* destination address, *default* TON and *default* NPI from *default* source address, *default* TON and *default* NPI on *now*. Request delivery receipt *default*. Select SMS Gateway *default*.

Mode

Wireless mode with the SMS:SMPP function:

Syntax

```
send SMS `message` to `dest_address` destination address, `ton` TON and
`npi` NPI from `source_address` source address, `ton` TON and `npi` NPI on
delivery-day. Request delivery receipt `receipt`. Select SMS Gateway
`sms_gateway`.
```

Parameters

message

String. This text may contain policy parameters (described later in this section) to perform parameter substitution within the message text.

dest_address

String. If not the default, this overrides the configured address. You can specify *dest_address* as one or more comma-separated static values, or as one or more comma-separated references to custom fields in the subscriber profile.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

ton

If not the default, this overrides the configured Type of Number. One of the following:

- **default** (default)
- **UNKNOWN**
- **INTERNATIONAL**
- **NATIONAL**
- **NETWORK SPECIFIC**
- **SUBSCRIBER NUMBER**
- **ALPHANUMERIC**
- **ABBREVIATED**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

npi

If not the default, this overrides the configured Number Plan Indicator. One of the following:

- **default** (default)
- **UNKNOWN**
- **ISDN (E163/E164)**
- **DATA (X.121)**
- **TELEX (F.69)**
- **LAND MOBILE (E.212)**
- **NATIONAL**
- **PRIVATE**
- **ERMES**
- **INTERNET (IP)**
- **WAP CLIENT ID**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

source_address

String. If not the default, this overrides the configured address.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

delivery-day

String. Enter a value in one of the following formats:

- **now** (default)—Keep the default value **now** to deliver the SMS immediately when the policy is triggered.
- **day**—Enter an integer between 1 and 31 to deliver the SMS on the specified day of the month. If the specified day of the month has passed for the current month, the SMS will be delivered on that day in the following month. If the specified day of the month does not exist in the current month, the SMS will be delivered on the last day of the month. Any value less than 1 or greater than 31 is invalid.
- **smart string**—Enable the **Evaluate as Expression** checkbox. In the **Value** field, enter an arithmetic expression containing one of the following policy parameters:
 - `{User.BillingDay}` —The billing day for the subscriber profile. Resolves to an integer between 1 and 31. If this parameter is used, the parameter `{User.custom_field}`, where *custom_field* is a configured custom subscriber profile field, may also be used if the custom field resolves to an integer value.
 - `{User.Pool.BillingDay}` —The billing day for the pool profile of the subscriber. Resolves to an integer between 1 and 31. If this parameter is used, the parameter `{User.Pool.custom_field}`, where *custom_field* is a configured custom pool profile field, may also be used if the custom field resolves to an integer value.

The arithmetic expression supports addition and subtraction and must not contain the default value **now**. The result will be evaluated with consideration to the number of days in the current month. For example, the expression `{User.BillingDay}-4` would deliver the SMS four days before the billing day for the subscriber. If the expression would result in the SMS being sent in the past, the SMS will not be sent.

**Note:**

Scheduled SMS delivery is only available when the billing type for the subscriber is monthly.

receipt

One of the following:

- **default** (default)—Use global default configured for this MPE device.
- **No Delivery Receipt**
- **Delivery Receipt on success and failure**
- **Delivery Receipt on failure**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

sms_gateway

Select the SMS gateway to use for the send action. **default** uses the default SMS gateway configured for the Policy Server.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Sends an SMS text message, with specified text, to the subscriber associated with the message.

Messages can be up to 254 characters long. If long message support is configured, SMS messages longer than 160 characters are split into segments and reassembled by the receiving device; messages of up to 1000 characters are supported. See the *Oracle Communications Policy Management Configuration Management Platform Wireless User's Guide* for information on configuring long message support.

**Note:**

Messages over 1000 characters are truncated.

The default source and destination address, TON, and NPI configured on the MPE device can be used or overridden.

To send notifications to multiple destinations, you can specify *dest_address* as one or more comma-separated static values, or as one or more comma-separated references to custom fields in the subscriber profile. Destinations must all be of the same type; this ensures that the same TON and NPI settings configured in the policy action will apply to all destinations. No transformations are performed on the subscriber's profile data by the MPE device, so custom fields used as alternate destinations must contain values formatted as required by the SMSC. Multivalued fields (LDAP attributes) are not supported.

If the addresses specified are not available (for example, if a custom field is not populated in the subscriber database), then the global default is used; if the global default is not configured, then the SMS message is sent to the MSISDN for the subscriber; if the MSISDN for the subscriber cannot be determined, then the SMS message is not sent and a trace log alert is generated.

You can request a receipt from the SMSC server, which will be logged in the file SMPP.log, when the message is delivered to the subscriber. You can request a receipt on success, failure, or in either case. See the *Oracle Communications Policy Management Configuration Management Platform Wireless User's Guide* for information on configuring delivery receipt default actions.

Example 36-25 Example

```
send SMS `you have reached 80%% of your quota` to `{User.MSISDN},
{User.AltDest1},{User.AltDest2}` destination address, `default` TON
and `default` NPI from `614` source address, `default` TON and
`default` NPI on `now`. Request delivery receipt `default`. Select SMS
Gateway `default`.
```

send SMS *specified* to *default* destination address, *default* TON and *default* NPI from *default* source address, *default* TON and *default* NPI on *Billing Day*. Request delivery receipt *default*. Select SMS Gateway *default*.

Mode

Wireless mode with the SMS:SMPP function:

Syntax

```
send SMS `message` to `dest_address` destination address, `ton` TON and
`npi` NPI from `source_address` source address, `ton` TON and `npi` NPI
`delivery-day`. Request delivery receipt `receipt`. Select SMS Gateway
`sms_gateway`.
```

Parameters

message

String. This text may contain policy parameters (described later in this section) to perform parameter substitution within the message text.

dest_address

String. If not the default, this overrides the configured address. You can specify *dest_address* as one or more comma-separated static values, or as one or more comma-separated references to custom fields in the subscriber profile.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

ton

If not the default, this overrides the configured Type of Number. One of the following:

- **default** (default)
- **UNKNOWN**
- **INTERNATIONAL**
- **NATIONAL**
- **NETWORK SPECIFIC**
- **SUBSCRIBER NUMBER**
- **ALPHANUMERIC**
- **ABBREVIATED**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

npi

If not the default, this overrides the configured Number Plan Indicator. One of the following:

- **default** (default)
- **UNKNOWN**
- **ISDN (E163/E164)**
- **DATA (X.121)**

- **TELEX (F.69)**
- **LAND MOBILE (E.212)**
- **NATIONAL**
- **PRIVATE**
- **ERMES**
- **INTERNET (IP)**
- **WAP CLIENT ID**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

source_address

String. If not the default, this overrides the configured address.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

delivery-day

String. Enter a value in one of the following formats:

- **Billing Day** (default)—Keep the default value **Billing Day** to deliver the SMS on the billing day for the subscriber. If the policy is triggered on the billing day for the subscriber, the SMS will be delivered on the current billing day.
- **day**—Enter an integer between 1 and 31 to deliver the SMS on the specified day of the month. If the specified day of the month has passed for the current month, the SMS will be delivered on that day in the following month. If the specified day of the month does not exist in the current month, the SMS will be delivered on the last day of the month. Any value less than 1 or greater than 31 is invalid.
- **smart string**—Enable the **Evaluate as Expression** checkbox. In the **Value** field, enter an arithmetic expression containing one of the following policy parameters:
 - `{User.BillingDay}` —The billing day for the subscriber profile. Resolves to an integer between 1 and 31. If this parameter is used, the parameter `{User.custom_field}`, where *custom_field* is a configured custom subscriber profile field, may also be used if the custom field resolves to an integer value.

- `{User.Pool.BillingDay}`—The billing day for the pool profile of the subscriber . Resolves to an integer between 1 and 31. If this parameter is used, the parameter `{User.Pool.custom_field}`, where *custom_field* is a configured custom pool profile field, may also be used if the custom field resolves to an integer value.

The arithmetic expression supports addition and subtraction and must not contain the default value `Billing Day`. The result will be evaluated with consideration to the number of days in the current month. For example, the expression `{User.BillingDay}-4` would deliver the SMS four days before the billing day for the subscriber. If the expression would result in the SMS being sent in the past, the SMS will not be sent.

**Note:**

Scheduled SMS delivery is only available when the billing type for the subscriber is monthly.

receipt

One of the following:

- **default** (default)—Use global default configured for this MPE device.
- **No Delivery Receipt**
- **Delivery Receipt on success and failure**
- **Delivery Receipt on failure**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

sms_gateway

Select the SMS gateway to use for the send action. **default** uses the default SMS gateway configured for the Policy Server.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Sends an SMS text message, with specified text, to the subscriber associated with the message on the billing day for the subscriber.

Messages can be up to 254 characters long. If long message support is configured, SMS messages longer than 160 characters are split into segments and reassembled by the receiving device; messages of up to 1000 characters are supported. See the *Oracle Communications Policy Management Configuration Management Platform Wireless User's Guide* for information on configuring SMPP long message support.



Note:

Messages over 1000 characters are truncated.

The default source and destination address, TON, and NPI configured on the MPE device can be used or overridden.

To send notifications to multiple destinations, you can specify `dest_address` as one or more comma-separated static values, or as one or more comma-separated references to custom fields in the subscriber profile. Destinations must all be of the same type; this ensures that the same TON and NPI settings configured in the policy action will apply to all destinations. No transformations are performed on the subscriber's profile data by the MPE device, so custom fields used as alternate destinations must contain values formatted as required by the SMSC. Multivalued fields (LDAP attributes) are not supported.

If the address(es) specified are not available (for example, if a custom field is not populated in the subscriber database), then the global default is used; if the global default is not configured, then the SMS message is sent to the MSISDN for the subscriber. If the MSISDN for the subscriber cannot be determined, then an SMS message is not sent and a trace log alert is generated.

You can request a receipt from the SMSC server, which will be logged in the file `SMPP.log`, when the message is delivered to the subscriber. You can request a receipt on success, failure, or in either case. See the *Oracle Communications Policy Management Configuration Management Platform Wireless User's Guide* for information on configuring delivery receipt default actions.

Example 36-26 Example

```
send SMS `you have reached 80%% of your quota` to
`{User.MSISDN},{User.AltDest1},{User.AltDest2}` destination
address, `default` TON and `default` NPI from `614` source
address, `default` TON and `default` NPI on Billing Day.
Request delivery receipt `Default`. Select SMS Gateway `default`.
```

send SMS *specified* to *default* destination address, from *default* source address on user billing day. Request delivery receipt *default*. Select SMS Gateway *default*.

Mode

Wireless mode with one of the following functions enabled:

- SMS:SMPP
- SMS:XML

- SMS:CMPP

Syntax

send SMS ``message`` to ``dest_address`` destination address, from ``source_address`` source address. Request delivery receipt ``receipt``. Select SMS Gateway ``sms_gateway``.

Parameters

message

String. This text may contain policy parameters (described later in this section) to perform parameter substitution within the message text.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

dest_address

String. If not the default, this overrides the configured address. You can specify `dest_address` as one or more comma-separated static values, or as one or more comma-separated references to custom fields in the subscriber profile.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

source_address

String. If not the default, this overrides the configured address.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

receipt

One of the following:

- **default** (default)

The Registered Delivery value is used. See the appropriate *Oracle Communications Policy Management Configuration Management Platform Wireless User's Guide*.

- **No Delivery Receipt**
- **Delivery Receipt**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

sms_gateway

Select the SMS gateway to use for the send action.



Note:

When the SMS:XML function is enabled, **default** is the only available option.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Sends an SMS text message, with specified text, to the subscriber associated with the message on the user billing day.

The default source and destination address configured on the MPE device can be used or overridden.

To send notifications to multiple destinations, you can specify *dest_address* as one or more comma-separated static values, or as one or more comma-separated references to custom fields in the subscriber profile. Destinations must all be of the same type. No transformations are performed on the profile data of the subscriber by the MPE device, so custom fields used as alternate destinations must contain values formatted as required by the SMSC. Multivalued fields (LDAP attributes) are not supported.

If the addresses specified are not available (for example, if a custom field is not populated in the subscriber database), then the global default is used; if the global default is not configured, then the SMS message is sent to the MSISDN for a subscriber; if the MSISDN for the subscriber cannot be determined, then no SMS message is sent and a trace log alert is generated.

send SMS *specified* to *default* destination address, from *default* source address. Request delivery receipt *default*. Select SMS Gateway *default*.

Mode

Wireless mode with one of the following functions enabled:

- SMS:SMPP
- SMS:XML
- SMS:CMPP

Syntax

send SMS *message* to *dest_address* destination address, from *source_address* source address. Request delivery receipt *receipt*. Select SMS Gateway *sms_gateway*

Parameters

message

String. This text may contain policy parameters (described later in this section) to perform parameter substitution within the message text.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

dest_address

String. If not the default, this overrides the configured address. You can specify *dest_address* as one or more comma-separated static values, or as one or more comma-separated references to custom fields in the subscriber profile.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

source_address

String. If not the default, this overrides the configured address.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

receipt

One of the following:

- **default** (default)—Uses global default configured for this MPE device. Uses the Registered Delivery global default which is configured in SMS profile section of the **Policy Server** tab.
- **No Delivery Receipt**—Does not request a delivery receipt when sending an SMS message.
- **Delivery Receipt**—Requests a delivery receipt when sending an SMS message.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

sms_gateway

Select the SMS gateway to use for the send action.



Note:

When the SMS:XML function is enabled, **default** is the only available option.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Sends an SMS text message, with specified text, to the subscriber associated with the message.

The default source and destination address configured on the MPE device can be used or overridden.

To send notifications to multiple destinations, you can specify *dest_address* as one or more comma-separated static values, or as one or more comma-separated references to custom fields in the subscriber profile. Destinations must all be of the same type. No transformations are performed on the subscriber's profile data by the MPE device, so custom fields used as alternate destinations must contain values formatted as required by the SMSC. Multivalued fields (LDAP attributes) are not supported.

If the addresses specified are not available (for example, if a custom field is not populated in the subscriber database), then the global default is used; if the global default is not configured, then the SMS message is sent to the MSISDN for the subscriber; if the MSISDN for the subscriber cannot be determined, then no SMS message is sent and a trace log alert is generated.

Example 36-27 Example

The following example uses a custom field named Custom7 in the User.Pool object, defined in an SPR, of comma-separated MSISDN values to send a notification message to all members of a subscriber pool:

```
send SMS `1 GB of data has been granted to your subscriber pool.` to
`{User.Pool.Custom7}` destination
address, from `default` source address. Request delivery receipt `default`.
```

Because a custom field is limited to 255 characters, the list of MSISDNs in a large subscriber pool may require multiple variables. The following example uses a series of custom fields in the User.Pool object, defined in an SPR, each containing comma-separated MSISDN values, to send a message to all members of a large subscriber pool:

```
send SMS `1 GB of data has been granted to your subscriber pool.` to
`{User.Pool.Custom7},{User.Pool.Custom8},{User.Pool.Custom9}` destination
address, from `default` source address. Request delivery receipt `default`.
Select SMS Gateway `default`.
```

send SMS *specified* to user from *default* source address if exceed *number* *days* for *Identity*. Request delivery receipt *default*. Select SMS Gateway *default*.

Mode

Wireless mode with one of the following functions enabled:

- SMS:SMPP
- SMS:XML
- SMS:CMPP

Syntax

```
send SMS `message` to user from `source_address` source address, if exceed
`number` `days` for `identity`. Request delivery receipt `receipt`. Select SMS
Gateway `sms_gateway`.
```

Parameters

message

String. This text can contain policy parameters (described later in this section) to perform parameter substitution within the message text.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

source_address

String. If not the default, this overrides the configured address. To specify the the default, enter `default`. The default uses the value of the attribute `smpp.protocol.srcId` configured in the `SMPP.properties` file.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

number

Positive integer.

days

The calculated datetime is expressed in this granularity:

- **days** (default)
- **hours**

Identity

String. Identifies different types of SMS messages. Must be less than 20 characters.

receipt

One of the following:

- **default** (default)—Uses global default configured for this MPE device. Uses the Registered Delivery global default which is configured in SMS profile section of the **Policy Server** tab.
- **No Delivery Receipt**—Does not request a delivery receipt when sending an SMS message.
- **Delivery Receipt**—Requests a delivery receipt when sending an SMS message.

sms_gateway

Select the SMS gateway to use for the send action.

**Note:**

When the SMS:XML function is enabled, **default** is the only available option.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Sends an SMS text message to an end user once during the configured interval.

You can request a receipt from the SMSC server, which will be logged in the CMPP.log or SMPP.log file, when the message is delivered to the subscriber. You can also request a receipt. See the *Oracle Communications Policy Management Configuration Management Platform Wireless User's Guide* for information on configuring delivery receipt default functions.

The last delivery time for each type of SMS message (specified in the *Identity* variable) is listed on the **State** tab of the **Profile Data** in the **SPR** section of the navigation pane.

Example 36-28 Example

```
where the request is creating a new session
And where the session is an enforcement session
And where the Cell Identifier matches one of 110
send SMS `Message 1` to user from `default` source address if exceed `1`
`hours` for `usecase1`.
Request delivery receipt `default`. Select SMS gateway `default`.
send SMS `Message 2` to user from `default` source address if exceed `1`
`hours` for `usecase2`. Request delivery receipt `default`.
send SMS `Message 3` to user from `default` source address if exceed `1`
`hours` for `usecase3`. Request delivery receipt `default`.
continue processing message
```

send SMS *specified* to user on *now*. Request delivery receipt *default*.
Select SMS Gateway *default*.

Mode

Wireless mode with at least one of the following functions enabled:

- SMS:SMPP
- SMS:XML

Syntax

send SMS ``message`` to user on ``delivery-day``. Request delivery receipt ``receipt``. Select SMS Gateway ``sms_gateway``.

Parameters

message

String. This text may contain policy parameters (described later in this section) to perform parameter substitution within the message text. If you select **Evaluate as expression**, the text in the field is evaluated as an arithmetic expression, and the result is used.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

delivery-day

String. Enter a value in one of the following formats:

- **now** (default)—Keep the default value `now` to deliver the SMS immediately when the policy is triggered.
- **day**—Enter an integer between 1 and 31 to deliver the SMS on the specified day of the month. If the specified day of the month has passed for the current month, the SMS will be delivered on that day in the following month. If the specified day of the month does not exist in the current month, the SMS will be delivered on the last day of the month. Any value less than 1 or greater than 31 is invalid.
- **smart string**—Enable the **Evaluate as Expression** checkbox. In the **Value** field, enter an arithmetic expression containing one of the following policy parameters:
 - `{User.BillingDay}`—The billing day for the subscriber profile. Resolves to an integer between 1 and 31. If this parameter is used, the parameter `{User.custom_field}`, where `custom_field` is a configured custom subscriber profile field, may also be used if the custom field resolves to an integer value.
 - `{User.Pool.BillingDay}`—The billing day for the pool profile of the subscriber. Resolves to an integer between 1 and 31. If this parameter is used, the parameter `{User.Pool.custom_field}`, where `custom_field` is a configured custom pool profile field, may also be used if the custom field resolves to an integer value.

The arithmetic expression supports addition and subtraction and must not contain the default value `now`. The result is evaluated with consideration to the number of days in the current month. For example, the expression `{User.BillingDay}-4` delivers the SMS four days before the billing day for the subscriber. If the expression would result in the SMS being sent in the past, the SMS will not be sent.

**Note:**

Scheduled SMS delivery is only available when the billing type for the user is monthly.

receipt

One of the following:

- **default** (default)—Uses global default configured for this MPE device. Uses the Registered Delivery global default which is configured in SMS profile section of the **Policy Server** tab.
- **No Delivery Receipt**—Does not request a delivery receipt when sending an SMS message.
- **Delivery Receipt on success and failure**—Always delivers a receipt.
- **Delivery Receipt on failure**—Delivers a receipt only when there is a failure.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

sms_gateway

Select the SMS gateway to use for the send action.

**Note:**

When the SMS:XML function is enabled, **default** is the only available option.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Sends an SMS text message, with specified text, to the subscriber associated with the message.

In SMPP mode, messages can be up to 254 characters long. If SMPP long message support is configured, SMS messages longer than 160 characters are split into segments and reassembled by the receiving device; messages of up to 1000 characters are supported. See the appropriate *Oracle Communications Policy Management Configuration Management Platform Wireless User's Guide* for information on configuring SMPP long message support.

**Note:**

Messages over 1000 characters are truncated.

You can request a receipt from the SMSC server, which will be logged in the file SMPP.log, when the message is delivered to the subscriber. You can request a receipt on success, failure, or in either case. See the *Oracle Communications Policy Management Configuration Management Platform Wireless User's Guide* for information on configuring delivery receipt default functions.

Example 36-29 Example

```
send SMS `you have reached 80%% of your quota` to user on  
`{User.BillingDay}-4`. Request delivery receipt `Default`. Select SMS  
Gateway `default`.
```

send SMS *specified* to user on *Billing Day*. Request delivery receipt *default*. Select SMS Gateway *default*.

Mode

Wireless mode with of the following functions enabled:

- SMS:SMPP
- SMS:XML
- SMS:CMPP

Syntax

```
send SMS `message` to user on `delivery-day`. Request delivery receipt  
`receipt`. Select SMS Gateway `sms_gateway`.
```

Parameters***message***

String. This text may contain policy parameters (described later in this section) to perform parameter substitution within the message text. If you select **Evaluate as expression**, the text in the field is evaluated as an arithmetic expression, and the result is used.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

delivery-day

String. Enter a value in one of the following formats:

- **Billing Day (default)**—Keep the default value `Billing Day` to deliver the SMS on the billing day for the subscriber . If the policy is triggered on the billing day for the subscriber, the SMS is delivered on the current billing day.
- **day**—Enter an integer between 1 and 31 to deliver the SMS on the specified day of the month. If the specified day of the month has passed for the current month, the SMS will be delivered on that day in the following month. If the specified day of the month does not exist in the current month, the SMS will be delivered on the last day of the month. Any value less than 1 or greater than 31 is invalid.
- **smart string**—Enable the **Evaluate as Expression** checkbox. In the **Value** field, enter an arithmetic expression containing one of the following policy parameters:
 - `{User.BillingDay}` — The billing day for the subscriber profile. Resolves to an integer between 1 and 31. If this parameter is used, the parameter `{User.custom_field}`, where *custom_field* is a configured custom subscriber profile field, may also be used if the custom field resolves to an integer value.
 - `{User.Pool.BillingDay}`—The billing day for the pool profile of the subscriber . Resolves to an integer between 1 and 31. If this parameter is used, the parameter `{User.Pool.custom_field}`, where *custom_field* is a configured custom pool profile field, may also be used if the custom field resolves to an integer value.

The arithmetic expression supports addition and subtraction and must not contain the default value `Billing Day`. The result will be evaluated with consideration to the number of days in the current month. For example, the expression `{User.BillingDay}-4` would deliver the SMS four days before the billing day for the subscriber. If the expression would result in the SMS being sent in the past, the SMS will not be sent.



Note:

Scheduled SMS delivery is only available when the billing type for the subscriber is monthly.

receipt

One of the following:

- **default (default)**—Uses global default configured for this MPE device. Uses the Registered Delivery global default which is configured in SMS profile section of the **Policy Server** tab.
- **No Delivery Receipt**—Does not request a delivery receipt when sending an SMS message.
- **Delivery Receipt on success and failure**—Always delivers a receipt.
- **Delivery Receipt on failure**—Delivers a receipt only when there is a failure.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

sms_gateway

Select the SMS gateway to use for the send action.



Note:

When the SMS:XML function is enabled, **default** is the only available option.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Sends an SMS text message, with specified text, to the subscriber associated with the message on the billing day for the subscriber.

In SMPP mode, messages can be up to 254 characters long. If SMPP long message support is configured, SMS messages longer than 160 characters are split into segments and reassembled by the receiving device; messages of up to 1000 characters are supported. See the *Oracle Communications Policy Management Configuration Management Platform Wireless User's Guide* for information on configuring SMPP long message support.



Note:

Messages over 1000 characters are truncated.

You can request a receipt from the SMSC server, which will be logged in the file `SMPP.log`, when the message is delivered to the subscriber. You can request a receipt on success, failure, or in either case. See the *Oracle Communications Policy Management Configuration Management Platform Wireless User's Guide* for information on configuring delivery receipt default functions.

Example 36-30 Example

```
send SMS `you have reached 80%% of your quota` to user on `Billing
Day`. Request delivery receipt `Default`. Select SMS Gateway `default`.
```

send SMS *specified* to user. Request delivery receipt *default*. Select SMS Gateway *default*.

Mode

Wireless mode with at least one of the following functions enabled:

- SMS:SMPP
- SMS:XML
- SMS:CMPP

Syntax

send SMS *message* to user. Request delivery receipt *receipt*. Select SMS Gateway *sms_gateway*.

Parameters

message

String. This text may contain policy parameters (described later in this section) to perform parameter substitution within the message text. If you select **Evaluate as expression**, the text in the field is evaluated as an arithmetic expression, and the result is used.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

receipt

One of the following:

- **default** (default) — The value in the Registered Delivery field configured in the protocol options is used. See the *Oracle Communications Policy Management Configuration Management Platform Wireless User's Guide* for information on configuring protocol options.
- **No Delivery Receipt**
- **Delivery Receipt**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

sms_gateway

Select the SMS gateway to use for the send action.

**Note:**

When the SMS:XML function is enabled, **default** is the only available option.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Sends an SMS message, with specified text, to the subscriber associated with the message.

Example 36-31 Example

```
send SMS `you have reached 80%% of your quota` to user. Request  
delivery receipt `Default`. Select SMS Gateway `default`.
```

send SMTP message with the following *text/plain* content

Mode

Wireless mode with SMS:SMPP or SMS:XML function enabled.

Syntax

```
send SMTP message with the following format content: To: to_address CC:  
cc_address BCC: bcc_address From: from_address Reply-To: reply_address  
Subject: subject Text: message Signature: signature
```

Parameters***format***

One of the following:

- **text/plain** (default) — The email is in plain-text format.
- **text/html** — The email includes HTML formatting.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

to_address

String. If not the default, this overrides the configured address. You can specify up to five comma-separated static values, or up to five comma-separated references to custom fields in the subscriber profile.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

cc_address

String. If not the default, this overrides the configured address. You can specify up to five comma-separated static values, or up to five comma-separated references to custom fields in the subscriber profile.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

bcc_address

String. If not the default, this overrides the configured address. You can specify up to five comma-separated static values, or up to five comma-separated references to custom fields in the subscriber profile.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

from_address

String. The address of the author who sent the mail.



Note:

You may not necessarily want the reply to come back from this address. This can be configured globally to a default value.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

reply_address

String. If not the default, this overrides the configured address.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

subject

String.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

message

String. Body of the message.

signature

String. If not `default`, this overrides the configured signature block.

Description

Sends an email message, with the specified text and signature block, to the subscriber associated with the address. The message is sent through an SMS Relay (SMSR) interface.

To send email to multiple destinations, you can specify up to five addresses (any combination of *to_address*, *cc_address*, or *bcc_address*) as comma-separated static values, or as comma-separated references to custom fields in the subscriber profile. You can specify up to five addresses. Destinations must all be of the same type. No transformations are performed on the subscriber's profile data by the MPE device, so

custom fields used as alternate destinations must contain values formatted as required by the SMSR. Multivalued fields (LDAP attributes) are not supported.

If the address(es) specified are not available (for example, if a custom field is not populated in the subscriber database), then the global default is used; if the global default is not configured, then no SMTP message is sent and an SMTP log alert is generated. See the *CMP Wireless User's Guide* for information on configuring SMTP default values.

set alarm with severity *severity level*, id *unique alarm identifier* and message *message text*

Mode

Cable, Wireless

Syntax

```
set alarm with severity level, id alarm-id and message message
```

Parameters

level

One of the following:

- **Critical** (ID 74000)
- **Major** (ID 74001)
- **Minor** (ID 74002)



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

alarm-id

The alarm ID. If you select **Evaluate as expression**, the text in the field is evaluated as an arithmetic expression, and the result is used.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

message

String. This text may contain policy parameters (described later in this section) to perform parameter substitution within the message text. If you select **Evaluate as expression**, the text in the field is evaluated as an arithmetic expression, and the result is used.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Sends an alarm to the CMP system containing the specified severity level and message text. This alarm is written to the Alarm History Report, and will appear in the Active Alarms display for one hour, until cleared, or unless the server fails over, whichever comes first. Alarms generated by policy actions do not affect the HA score of a server, and will not cause a failover. For more information, see the appropriate *CMP User's Guide*.

set authorization validity time to # seconds

Mode

Wireless

Syntax

```
set authorization validity time to seconds seconds
```

Parameters**seconds**

A numeric value that specifies time in units of seconds.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Sets the authorization expiration time (in seconds) after which the enforcement device requests re-authorization from the MPE device for the requested user's service.

set authorization validity time to *datetime*

Mode

Wireless

Syntax

```
set authorization validity time to datetime
```

Parameters

datetime

One of the following:

- A policy variable.
- **now** (default) — The local date-time.
- A date-time in the format: `yyyy-mm-ddThh:mm:ss+UTCOffset`.

Note:

Enter the date-time directly into the field or click the calendar icon for assistance:

- **Date**—Select the date from the calendar interface.
- **Time**—Select hh:mm:ss.
- **UTC Offset**—Select number of hours before or after UTC time to start.
- **now**—Select for the local date-time.
- **Time only**—Select to use the time only.

- A JavaScript code snippet — Enter a JavaScript statement that evaluates to a date-time in the format: `yyyy-mm-ddThh:mm:ss+UTCOffset`. Click **Evaluate as expression** to bypass date-time format validation.

Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Sets the authorization expiration time (to the quarter hour) after which the enforcement device requests re-authorization from the MPE device for the requested user's service.

set authorization validity time to *time on day* using *configured local time*

Mode

Wireless

Syntax

set authorization validity time to *time on day-of-week* using *time-zone*

Parameters

time

A time, in the format *hh:mm* (limited to 15-minute intervals).



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

day-of-week

One of the following:

- **Sunday**
- **Monday**
- **Tuesday**
- **Wednesday**
- **Thursday**
- **Friday**
- **Saturday**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

time-zone

One of the following:

- **CONFIGURED LOCAL TIME** (default)—Calculate the time from the location configured for this MPE device
- **SYSTEM LOCAL TIME**—Calculate the time from the location of this MPE device
- **USER LOCAL TIME**—Calculate the time from the location configured for the user equipment's location



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Sets the authorization expiration time (to the quarter hour) after which the enforcement device requests re-authorization from the MPE device for the requested user's service. If time-zone information is available from the user equipment, time can be calculated from either the MPE device or the user equipment's location.

set charging server(s) for the IP-CAN/Sd session to *specified values*

Mode

Wireless

Syntax

set charging server(s) for the IP-CAN/Sd session to *charging-server-name*

Parameters***charging-server-name***

Names of charging servers that are defined in the CMP database.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Sets the charging servers, as specified. To define a charging server, see the *CMP Wireless User's Guide*.

Example 36-32 Example

```
set charging server(s) for the IP-CAN/Sd session to Primary Online
Server:ocs_1, Secondary Online Server:ocs_2
```

set CSG reporting info to *select value*

Mode

Wireless

Syntax

set CSG reporting info to *info-type*

Parameters

info-type

- **CHANGE_CSG_CELL** — Indicates that the PCEF reports the user CSG information change to the charging domain when the UE enters/leaves/accesses via a CSG cell.
- **CHANGE_CSG_SUBSCRIBED_HIBRID_CELL** — Indicates that the PCEF reports the user CSG information change to the charging domain when the UE enters/leaves/accesses via a hybrid cell in which the subscriber is a CSG member
- **CHANGE_CSG_UNSUBSCRIBED_HIBRID_CELL** — Indicates that the PCEF reports the user CSG information change to the charging domain when the UE enters/leaves/accesses via a hybrid cell in which the subscriber is not a CSG member.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Sent from the MPE device to the PCEF to request the PCEF to report the user CSG information change to the charging domain.

set custom AVP *name* value to the policy context property *name*

Mode

Wireless

Syntax

set custom AVP *avp-name* value to the policy context property *property-name*

Parameters

avp-name

An existing AVP Name and Vender ID, or an AVP name from an existing Policy Table.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

property-name

String that represents the policy context property.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Makes the AVP value accessible throughout the policy context so other policies can access this AVP value as a context property. The context property variable will be set only if this AVP exists in the request and its value is not null.

set custom AVP *name* value to the user property *name* and save *always*

Mode

Wireless

Syntax

set custom AVP *avp-name* value to the user property *property-name* and save *save-mode*

Parameters***avp-name***

An existing AVP Name and Vender ID, or an AVP name from an existing Policy Table.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

property-name

String.

Up to 255 characters that represents a user property.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

save-mode

One of the following:

- **always** (default)
- **unless rejected**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Sets an AVP value as a User object property to persist between sessions.

set DRMP AVP to *DRMP Level* in Re-Authorized Request

Mode

Wireless mode with the 3GPP mode enabled.

Syntax

```
set DRMP AVP to drmp-level in Re-Authorized Request
```

Parameters***drmp-level***

The Diameter routing message priority (DRMP) priority. Select one of the values from the list, where PRIORITY_0 is the highest priority and PRIORITY_15 is the lowest priority.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Sets the priority level of the DRMP AVP for Gx: RAR messages.

Example 36-33 Example

where the requested session reservation priority is one of *DEFAULT*
And where the request MPS Identifier matches one of
MPSID1,MPSID2,MPSID3,MPSID4

```
set DRMP AVP to PRIORITY_0 in Re-Authorized Request  
continue processing message
```

set enterprise service path ID to value for the Gx session

Mode

Cable, Wireless

Syntax

```
set Enterprise-Service-Path-ID to value for the Gx session
```

Parameter

value

String



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Sets the Enterprise-Service-Path-ID to a specified value for the Gx sessions. The value is stored as the EnterpriseServicePathID attribute of the Gx session.

Examples

A example of policy for mapping a subscriber profile attribute to Gx enterprise service path ID:

```
where the request is creating a new session, modifying an existing session, re-  
authorizing an existing session And where the session is an enforcement  
session And where the session is Custom1 is available set enterprise service path  
ID to {User.Custom1} for the Gx session continue processing message
```

set external field to # percent of select type for selected quota

Mode

Cable, Wireless

Syntax

```
set field to value percent of type for quota-name quota
```

Parameters

field

String name of field in external database.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

value

New string name of field in external database.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

type

One of the following:

- **service-specific**
- **time**
- **total volume**
- **uplink volume**
- **downlink volume**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

quota-name

Name(s) of quota defined in the CMP database.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Sets a field in an external database to a percentage of the time, total volume, or service-specific quota of one or more selected quotas. This can be an LDAP server or an SPR. The MPE device on which this policy is executed must have write access to the database, and the external field must be defined on the MPE device. For more information, see the appropriate *CMP User's Guide*. See [Managing Quotas](#) for information on quotas.

set external field to `value`

Mode

Cable, Wireless

Syntax

```
set field to `value`
```

Parameters***field***

String name of field in external database.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

value

String.

Value specifies a field in the external database. If you select **Evaluate as expression**, the text in the field is evaluated as an arithmetic expression, and the result is used.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Sets the value of a field in an external database. This can be an LDAP server or, in wireless mode, an SPR. The MPE device on which this policy is executed must have write access to the database, and the external field must be defined on the MPE device. For more information, see the appropriate *CMP User's Guide*.

Example 36-34 Examples (Wireless Mode)

```
set Quota Volume to `{User.Quota.Gold.Volume}`
```

```
set Last Session to `{Date(2012-10-24 19:54:01)}`
```

set NoOptimization to request

Mode

Wireless

Syntax

```
set NoOptimization to request
```

Parameters

None

Description

Prevents the RAR optimization mechanism from being applied to a request. This functionality allows an RAR request to be sent to the MPE device without being impacted by optimization priorities.

set policy context property *name* to the instance name of dynamic quota of *selected* being used

Mode

Wireless

Syntax

```
set the policy context property-name to the instance name of dynamic  
quota-name being used
```

Parameters

property-name
String.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

quota-name

Name(s) of quota defined in the CMP database.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Sets the instance ID of the dynamic quota being used for the specified quota profile into a policy context property. See [Managing Quotas](#) for information on quotas.

set policy context property *name* to *value*

Mode

Cable, Wireless, Wireline

Syntax

```
set policy context property property-name to value
```

Parameters***property-name***

String.

May contain policy rule variables (see [Policy Rule Variables](#)) to perform parameter substitution within the property name.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

value

String.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Sets a subscriber property.

set Quota Exhaustion Action to *specified*

Mode

Wireless

Syntax

```
set Quota Exhaustion Action to action
```

Parameters***action***

Specifies the action the GGSN takes when a subscriber reaches the quota grant. Selecting this parameter opens a window with the following options:

Choose the Quota Exhaustion Action:

Quota Exhaustion Action	TERMINATE
Restriction Filters	
Filter ID List	
Redirect Server Type	IPV4
Redirect Server Address	

OK Cancel Use Policy Table

- **Quota Exhaustion Action** — Select one of the following:
 - **TERMINATE** (default) — Terminate the subscriber's session. If you select this option, the other options are not applicable.
 - **REDIRECT** — Redirect the session to another server. If you select this option, configure the following additional fields:

- * **Redirect Server Type** — Select **IPV4** (default), **IPV6**, **URL**, or **SIP URI**
- * **Redirect Server Address** — Type the server address
- **RESTRICT ACCESS** — If you select this option, additional configuration fields appear:
 - * **Restriction Filters** — Type a comma-separated list of Diameter IP Filter rules
 - * **Filter ID List** — Type a comma-separated list of named filters on the GGSN

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Sets the action to take if the subscriber's quota is exhausted. See [Managing Quotas](#) for information on quotas.

set session revalidation time to # seconds

Mode

Wireless

Syntax

```
set session revalidation time to seconds seconds
```

Parameters***seconds***

A numeric value that specifies time in units of seconds.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Provisions the session revalidation time to the number of seconds from when the policy executes.

set session revalidation time to Policy Counter ID(s) *select name(s)*

Mode

Wireless

Syntax

```
session revalidation time to Policy Counter IDs counter -name
```

Parameters

counter -name

- Select **Policy Counter Id** to select one or more policy counter ID defined in the CMP database.
- Select **Policy Counter ID(s)(CSV)** to enter a comma-separated string of policy counter IDs.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Provisions the session revalidation time to the value in the specified policy counter ID or IDs.

set session revalidation time to *time on day* using *configured local time*

Mode

Wireless

Syntax

```
set session revalidation time to time on day-of-week using time-zone
```

Parameters

time

A time, in the format *hh:mm* (limited to 15-minute intervals).



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

day-of-week

One of the following:

- **Sunday**
- **Monday**
- **Tuesday**
- **Wednesday**
- **Thursday**
- **Friday**
- **Saturday**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

time-zone

One of the following:

- **CONFIGURED LOCAL TIME** (default)—Calculate the time from the location configured for this MPE device
- **SYSTEM LOCAL TIME**—Calculate the time from the location of this MPE device
- **USER LOCAL TIME**—Calculate the time from the location configured for the user equipment's location



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Sets the session revalidation time (to the quarter hour) after which the enforcement device requests revalidation from the MPE device for the requested user's service. If time-zone information is available from the user equipment, time can be calculated from either the MPE device or the user equipment's location.

set *specified* ARP to *value*

Mode

Wireless mode with Diameter 3GPP function.

Syntax

```
set arp_type ARP to arp_attribute
```

Parameters

arp_type

Select the ARP session type.

GCS

The Group Communication Service (GCS) feature.

eMPS

The enhanced Multimedia Priority Service (eMPS) feature.

arp_attribute

Priority Value

Defines the relative importance of a resource request. Enter a value from 1 to 15.
The default is 1.

Preemption Capability

Defines whether a service data flow can get resources that were assigned to another service data flow with a lower priority level. Select **Enable** or **Disable**.
The default is **Enable**.

Preemption Vulnerability

Defines whether a service data flow can release the assigned resources so that a service data flow with a higher priority level can be admitted. Select **Enable** or **Disable**. The default is **Disable**.

Description

Overrides the default ARP settings for eMPS or GCS ARP.

set the *scope* state variable *name* to *now* + *0* days rounded up with *same* granularity using *configured local time* and save *always*

Mode

Wireless

Syntax

```
set the scope state variable variable-name to datetime direction duration  
granularity1 rounded rounding with granularity2 granularity using time-  
zone and save save-mode
```

Parameters

scope

One of the following:

- **subscriber**—Subscribers in the remote SPR.
- **pool**—Subscriber pool defined in the SPR.
- **subscriber_local**—Subscribers in the local MPE.
- **session**—Session variables that have a value as long as the session they are associated with is open.
- **policy_evaluation**—Policy evaluation variables that last only for the duration of the policy evaluation cycle.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

variable-name

String.



Note:

Any string up to 32 ASCII characters in length if the scope is **subscriber_local** or **session**.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

datetime

One of the following:

- A policy variable.
- **now** (default)—The local date-time.
- A date-time in the format: `yyyy-mm-ddThh:mm:ss+UTCOffset`.

 Note:

Enter the date-time directly into the field or click the calendar icon for assistance:

- **Date**—Select the date from the calendar interface.
- **Time**—Select hh:mm:ss.
- **UTC Offset**—Select number of hours before or after UTC time to start.
- **now**—Select for the local date-time.
- **Time only**—Select to use the time only.

- A JavaScript code snippet—Enter a JavaScript statement that evaluates to a date-time in the format: `yyyy-mm-ddThh:mm:ss+UTCoffset`. Click **Evaluate as expression** to bypass date-time format validation.

 Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

direction

One of the following, indicating a time offset in the future or past:

- **+** (default)
- **-**

duration

Positive integer.

 Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

granularity1

The offset is expressed in this granularity:

- **days** (default)
- **months**
- **hours**

- **minutes**

rounding

One of the following, indicating rounding up or down:

- **up** (default)
- **down**

granularity2

The calculated date-time is expressed in this granularity:

- **same** (default)
- **months**
- **days**
- **hours**
- **minutes**

time-zone

One of the following:

- **CONFIGURED LOCAL TIME** (default)—Calculate the time from the location configured for this MPE device
- **SYSTEM LOCAL TIME**—Calculate the time from the location of this MPE device
- **USER LOCAL TIME**—Calculate the time from the location configured for the user equipment's location



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

save-mode

One of the following:

- **always** (default)
- **unless rejected**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Sets and saves a state date-time variable to either the current date and time or another date-time and an offset. If time-zone information is available from the user equipment, time can be

calculated from either the MPE device or the location of the user equipment. You can specify that the variable is not saved if the policy rejects the message.

set the *scope* state variable *name* to *now* using *configured local time* and save *always*

Mode

Wireless

Syntax

set the *scope* state variable *variable-name* to *datetime* using *time-zone* and save *save-mode*

Parameters

scope

One of the following:

- **subscriber**—Subscribers in the remote SPR.
- **pool**—Subscriber pool defined in the SPR.
- **subscriber_local**—Subscribers in the local MPE.
- **session**—Session variables that have a value as long as the session they are associated with is open.
- **policy_evaluation**—Policy evaluation variables that last only for the duration of the policy evaluation cycle.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

variable-name

String.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

datetime

One of the following:

- A policy variable.
- **now** (default)—The local date-time.
- A date-time in the format: `yyyy-mm-ddThh:mm:ss+UTCOffset`.

 Note:

Enter the date-time directly into the field or click the calendar icon for assistance:

- **Date**—Select the date from the calendar interface.
- **Time**—Select hh:mm:ss.
- **UTC Offset**—Select number of hours before or after UTC time to start.
- **now**—Select for the local date-time.
- **Time only**—Select to use the time only.

- A JavaScript code snippet—Enter a JavaScript statement that evaluates to a date-time in the format: `yyyy-mm-ddThh:mm:ss+UTCOffset`. Click **Evaluate as expression** to bypass date-time format validation.

 Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

time-zone

One of the following:

- **CONFIGURED LOCAL TIME** (default)—Calculate the time from the location configured for this MPE device
- **SYSTEM LOCAL TIME**—Calculate the time from the location of this MPE device
- **USER LOCAL TIME**—Calculate the time from the location configured for the user equipment's location

 Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

save-mode

One of the following:

- **always** (default)
- **unless rejected**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Sets and saves a state variable timestamp to the current local time or a timestamp. If time-zone information is available from the SPR, time can be calculated from either the MPE device or the SPR device location. You can specify that the variable is not saved if the policy rejects the message.

set the *scope* state variable *name* to property *name* + *multiple of 0* days rounded *up* with *same* granularity and save *always*

Mode

Wireless

Syntax

```
set the scope state variable variable-name to property property-name
direction multiplier duration granularity rounded rounding
withgranularity2 granularity and save save-mode
```

Parameters**scope**

One of the following:

- **subscriber**—Subscribers in the remote SPR.
- **pool**—Subscriber pool defined in the SPR.
- **subscriber_local**—Subscribers in the local MPE.
- **session**—Session variables that have a value as long as the session they are associated with is open.
- **policy_evaluation**—Policy evaluation variables that last only for the duration of the policy evaluation cycle.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

variable-name

String.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

property-name

String.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

direction

One of the following, indicating a time offset in the future or past:

- **+** (default)
- **-**

multiplier

One of the following:

- **multiple of** (default) — the duration is added repeatedly until the result is in the future
- **exactly** — the duration is added once

duration

Positive integer.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

granularity

The offset is expressed in this granularity:

- **days** (default)

- **months**
- **hours**
- **minutes**

rounding

One of the following, indicating rounding up or down:

- **up** (default)
- **down**

granularity2

The calculated date-time is expressed in this granularity:

- **same** (default)
- **months**
- **days**
- **hours**
- **minutes**

save-mode

One of the following:

- **always** (default)
- **unless rejected**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Offsets a scope date-time variable, either by the number of time units necessary to move the result into the future or by a specific number of time units.

- If the value of the first variable is in the future, either the exact offset, or one unit of the offset, is added.
- If the value of the first variable is in the past and you specify **+ multiple of**, the duration is repeatedly added until the result is in the future.
- If the result of the offset is in the past (for example, if you specify **+ exactly 1 day** and the result is still in the past), the action is ignored. You can specify that the property is not saved if the policy rejects the message.
- If the value of the second variable is null then the action is ignored.

set the *scope* state variable *name* to select traffic profile *name* and save *always*

Mode

Wireless

Syntax

set the *scope* state variable *variable-name* to select traffic profile *retry-profile* and save *save-mode*

Parameters

scope

One of the following:

- **subscriber**—Subscribers in the remote SPR.
- **pool**—Subscriber pool defined in the SPR.
- **subscriber_local**—Subscribers in the local MPE.
- **session**—Session variables that have a value as long as the session they are associated with is open.
- **policy_evaluation**—Policy evaluation variables that last only for the duration of the policy evaluation cycle.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

variable-name

String.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

retry-profile

Select a profile.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

save-mode

One of the following:

- **always** (default)
- **unless rejected**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Sets and saves a scope state variable to the specified traffic profile. You can specify that the variable is not saved if the policy rejects the message.

set the *scope* state variable *name* to *`value`* and save *always*

Mode

Wireless

Syntax

set the *scope* state variable *variable-name* to *`value`* and save *save-mode*

Parameters**scope**

One of the following:

- **subscriber**—Subscribers in the remote SPR.
- **pool**—Subscriber pool defined in the SPR.
- **subscriber_local**—Subscribers in the local MPE.
- **session**—Session variables that have a value as long as the session they are associated with is open.
- **policy_evaluation**—Policy evaluation variables that last only for the duration of the policy evaluation cycle.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

variable-name

String.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

value

String.

If you select **Evaluate as expression**, the text in the field is evaluated as an arithmetic expression, and the result is used.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

save-mode

One of the following:

- **always** (default)
- **unless rejected**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Sets and saves a state variable. You can specify that the variable is not saved if the policy rejects the message.

set the *scope* state variable *name* to *time plus* random value within # seconds and save *always*

Mode

Wireless

Syntax

set the *scope* state variable *variable-name* to *time-type time-variance*
random value within *seconds* seconds and save *save-mode*

Parameters**scope**

The scope of the variable. Select one of the following:

- **subscriber**—Subscriber variable in the remote SPR as long as the subscriber exists in the SPR. The variable must be named **User.State.variable**.
- **pool**—Quota pool variable defined on the SPR as long as the pool exists in the SPR. The variable must be named **User.Pool.State.variable**.
- **subscriber_local**—Subscriber variable in the local MPE device as long as the subscriber has at least one session on the MPE device. The variable must be named **User.LocalState.variable**.
- **session**—Session variable that has a value as long as the session it is associated with is open. The variable must be named **Session.State.variable**.
- **policy_evaluation**—Policy evaluation variables that last for the duration of the policy evaluation cycle. The variable must be named **Policy.Variable.variable**.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

variable-name

String—Name of the variable.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

time-type

Supports time configured as:

- **Specific Time**—Specifies settings:
 - Set date and time:
 - * A policy variable.
 - * **now** (default)—The local date and time.
 - * A date-time in the format: `yyyy-mm-ddThh:mm:ss+UTCOffset`.

**Note:**

Enter the date-time directly into the field or click the calendar icon for assistance:

- * **Date**—Select the date from the calendar interface.
- * **Time**—Select hh:mm:ss.
- * **UTC Offset**—Select number of hours before or after UTC time to start.
- * **now**—Select for the local date-time.
- * **Time only**—Select to use the time only.

- * A JavaScript code snippet—Enter a JavaScript statement that evaluates to a date-time in the format: `yyyy-mm-ddThh:mm:ss+UTCOffset`. Click **Evaluate as expression** to bypass date-time format validation.
- **Select Time Mode**—The optional time zone. Select one of the following:
 - * **N/A**
 - * **CONFIGURED LOCAL TIME**—Calculate the time from the location configured for this MPE device
 - * **SYSTEM LOCAL TIME**—Calculate the time from the location of this MPE device
 - * **USER LOCAL TIME** (default)—Calculate the time from the location configured for the user equipment's location
- **Relative Time**—Specifies the number of hours, minutes, or seconds from the current time to the execution time. Select the time unit (**Hours**, **Minutes**, or **Seconds**) and enter a positive integer. For example, select **Hours** and enter 12 to set the execution time to 12 hours from now. You can instead enter a policy rule variable.
- **Policy Counter ID**—Select one or more policy counter IDs defined in the CMP database; or enter a comma-separated string of policy counter IDs.
- **Day Of Week**—Specifies one or more days of the week, plus a time during the day:
 - **Choose the day(s) of the week to check:**

- * **Sunday**
- * **Monday**
- * **Tuesday**
- * **Wednesday**
- * **Thursday**
- * **Friday**
- * **Saturday**
- **Enter time:** The execution time during the day, in the form *hh:mm*.
- **Select Time Mode**—The optional time zone. Select one of the following:
 - * **N/A**
 - * **CONFIGURED LOCAL TIME**—Calculate the time from the location configured for this MPE device
 - * **SYSTEM LOCAL TIME**—Calculate the time from the location of this MPE device
 - * **USER LOCAL TIME** (default)—Calculate the time from the location configured for the user equipment's location

time-variance

Supports a randomization interval:

- **plus**
- **minus**
- **plus/minus**

seconds

A numeric value that specifies time in units of seconds.

Valid range is 0 to 1000000000.

save-mode

One of the following:

- **always (default)**
- **unless rejected**

Description

Sets a state variable with specified scope and name to a time with a specified time variance. To avoid message storms, you can specify that a random time value be used, within specified limits, for rule activation and execution; a random value is used in the time window you specify in *time-variance*.

Example 36-35 Example

The following example shows how you can define state variables and use them in policy actions which add conditional policy information, set re-validation time, and which install a PCC rule:

```
set the session state variable {Session.State.StartTimeRandVar} to
```

```
1Hour minus random value within 30 seconds and save always
set the session state variable {Session.State.EndTimeRandVar} to 2Hour minus
random value within 30 seconds and save always
add Conditional Policy Information with Execution-Time to
{Session.State.StartTimeRandVar} and parameters
Diameter APN-Aggregate-Max-Bitrate-DL 1000
revalidate the session at {Session.State.StartTimeRandVar} using CONFIGURED
LOCAL TIME
install pccrule1 PCC rule(s) for session active between
{Session.State.StartTimeRandVar} and {Session.State.EndTimeRandVar}
```

set the user property *name* to *Existing or New* custom AVP *name* and send *always*

Mode

Wireless

Syntax

set the user property *property-name* to *property-type* custom AVP *avp-name* and send *send-mode*

Parameters

property-name

String.

May contain policy rule variables (see [Policy Rule Variables](#)) to perform parameter substitution within the property name.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

property-type

One of the following:

- **Existing or New** (default)
- **New**

avp-name

Select an existing AVP Name and Vender ID, or an AVP name from an existing Policy Table.



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

send-mode

One of the following:

- **always** (default)
- **unless rejected**
- **if rejected**



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Sets the user property value for an outgoing AVP. If a user property with the corresponding name exists, the AVP will be sent in the reply message.

set threshold to # percent of *granted* quota for service-specific units

Mode

Wireless

Syntax

set threshold to *extended-percent* percent of *provided-quota* quota for service-specific units

Parameters

extended-percent

An extended, non-integer percentage that can exceed 100 (for example, 102.4%).



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

provided-quota

One of the following:

- **initial**
- **granted** (default)

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Sets a threshold, based on a percentage of the volume (in service-specific units) granted to the user, so that the enforcement device (for example, a GGSN) notifies the MPE device when the threshold is reached. This action works on multiple quotas. See [Managing Quotas](#) for information on quotas.

set threshold to # percent of *granted* quota for time

Mode

Wireless

Syntax

set threshold to *extended-percent* percent of *provided-quota* quota for time

Parameters***extended-percent***

An extended, non-integer percentage that can exceed 100 (for example, 102.4%).

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

provided-quota

One of the following:

- **initial**
- **granted** (default)

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Sets a threshold, based on a percentage of the time (in seconds) granted to the user, so that the enforcement device (for example, a GGSN) notifies the MPE device when the threshold is reached. This action works on multiple quotas. See [Managing Quotas](#) for information on quotas.

set threshold to # percent of *granted* quota for volume

Mode

Wireless

Syntax

set threshold to *extended-percent* percent of *provided-quota* quota for volume

Parameters***extended-percent***

An extended, non-integer percentage that can exceed 100 (for example, 102.4%).

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

provided-quota

One of the following:

- **initial**
- **granted** (default)

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Sets a threshold, based on a percentage of the volume (in bytes) granted to the user, so that the enforcement device (for example, a GGSN) notifies the MPE device when the threshold is reached. This action works on multiple quotas. See [Managing Quotas](#) for information on quotas.

set time limit to # seconds

Mode

Cable

Syntax

```
set time limit to seconds seconds
```

Parameters***seconds***

A numeric value that specifies time in units of seconds.

Valid range is 0 to 1000000000.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Overwrites the time limit in the current message. If there is no TimeLimit object in the current message, a new one is added with the specified value.

set value to *Existing or New* custom AVP name and send *always*

Mode

Wireless

Syntax

```
set value to avp-type custom AVP avp-name and send send-mode
```

Parameters***value***

String.

This string represents a third-party non-grouped AVP. Check **Evaluate as expression** to evaluate this value as an expression.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

avp-type

Select type of AVP name:

- **Existing** (default)
- **New**

avp-name

An existing AVP Name and Vender ID.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

send-mode

One of the following:

- **always** (default)
- **unless rejected**
- **if rejected**

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Adds the third-party non-grouped AVP to the current Diameter session with the specified value. If a third-party AVP value is set in the current Diameter session, it will be sent with the corresponding outgoing message. The value parameter must corresponds to the AVP data type, otherwise this AVP will not be set. If New is selected as the type of AVP name, every time this action is called a new AVP is added to the message, even if the AVP with the same name is present in the message.

set volume limit to # kilobytes

Mode

Cable

Syntax

```
set volume limit to bandwidth kilobytes
```

Parameters

bandwidth

A numeric value that specifies bandwidth in bits per second (bps). You can also specify the type to change the rate per second by specifying one of the following:

- **k**—kilobits per second
- **K**—kilobits per second
- **m**—megabits per second
- **M**—megabits per second
- **g**—gigabits per second
- **G**—gigabits per second



Note:

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Overwrites the volume limit in the current message. If there is no VolumeLimit object in the current message, a new one is added with the specified value.

set volume threshold to # bytes for *select quota*

Mode

Wireless

Syntax

```
set volume threshold to number bytes for quota-name
```

Parameters

number

A numeric value.

quota-name

Name(s) of quota defined in the CMP database.

Description

Provisions the usage threshold to the specified number of bytes for the selected quota profile. See [Managing Quotas](#) for information on quotas.

subscribe PRA change for *PRA area*

Mode

Wireless mode with the 3GPP mode enabled.

Syntax

```
subscribe PRA change for pra-areas
```

Parameters***pra-areas***

A single area or multiple specific PRA areas selected from the defined PRA areas, manually input, or Default.

- **CMP defined PRA lists**

Select one or more defined PRA lists

- **Manual Input**

Enter the identifier for the PRA in hexadecimal format or a custom PRA from a subscriber profile in the format *{User.CustomField}*. For information on creating custom fields in subscriber profiles, see the *CMP Wireless User's Guide*.

The manual input format for multiple PRAs is:

```
PRA
identifier1 [;PRA element list1],PRA identifier2 [; PRA element
list2],...
```

The format of PRA identifier and PRA Element List is according to section 8.108 of TS 29.274[9]. It is specified in Hexadecimal format. If only has a PRA identifier then the PRA area is a predefined PRA area. If both PRA identifier and PRA Element List exists then it is a UE-dedicated PRA Area. The manual input is typically used to input a temporally PRA area. The manual input can also be used to get a PRA area from Custom field of subscriber. For example, *{User.Custom4}*. If the operator wants to manually input a PRA area they need to get the Hexadecimal value for each. Different vendors/operators should interact or exchange PRA info using the Hexadecimal representation as defined in section 8.108 of TS 29.274[9].

The manual input format for a single PRA is:

```
PRA identifier [, PRA element list]
```

- **Default**

The PRA to which the user equipment is already subscribed, if any.

The Default option specifies using the default PRA area. The default PRA is the PRA area subscribed or provisioned by the PCRF for the UE during IP-CAN session life cycle. It is either a UE- dedicated or predefined PRA area. It can be a PRA area that is retrieved from the subscriber profile (normally UE-dedicated) or a PRA area defined in the CMP (normally predefined). When used , this Default option means to check whether the UE has subscribed to a PRA area but does not care what the PRA area is.

**Note:**

If you are using a policy table for this parameter, click **Use Policy Table**, choose the field (column) representing the parameter.

Click **OK**.

Description

Subscribes the user equipment to PRA changes in the specified PRA. If **default area** is selected as the definition for the parameter *pra*, subscribes the user equipment to PRA changes in the last subscribed PRA.

unsubscribe PRA change

Mode

Wireless mode with the 3GPP mode enabled.

Syntax

```
unsubscribe PRA change
```

Parameters

None

Description

Unsubscribes from PRA changes.

Policy Rule Variables

The MPE device supports policy rule variables within certain conditions and actions (for example, where the `policy context property`, `set policy context property`, and `send notification`), as well as in policy tables. During policy rule execution, variables are replaced with contextual information. Each time the policy rule is evaluated, the unique set of policy rule variable replacements is referred to as the policy context.

For information on policy rule variables, how to use them, and lists of available variables, see the *Policy Variables Reference*.