

Oracle® Communications

Cloud Native Configuration Console

Troubleshooting Guide



Release 24.2.5

F95825-06

July 2025

ORACLE®

Copyright © 2021, 2025, Oracle and/or its affiliates.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software, software documentation, data (as defined in the Federal Acquisition Regulation), or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs) and Oracle computer documentation or other Oracle data delivered to or accessed by U.S. Government end users are "commercial computer software," "commercial computer software documentation," or "limited rights data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, reproduction, duplication, release, display, disclosure, modification, preparation of derivative works, and/or adaptation of i) Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs), ii) Oracle computer documentation and/or iii) other Oracle data, is subject to the rights and limitations specified in the license contained in the applicable contract. The terms governing the U.S. Government's use of Oracle cloud services are defined by the applicable contract for such services. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle®, Java, MySQL, and NetSuite are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Inside are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Epyc, and the AMD logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

Contents

1	Introduction	
1.1	Overview	1
1.2	Reference	1
2	Logs	
2.1	Collecting Logs	1
2.2	Log Formats	1
2.3	Log Levels	4
2.4	Types of Logs	5
2.5	Examples of Logs	9
2.6	Configuring Security Logs	15
2.6.1	Accessing logs	15
2.6.1.1	Accessing Logs in Non OCI Deployment	15
2.6.1.2	Accessing logs in OCI Deployment	16
2.6.2	Debugging using Logs	19
3	Debug Tool	
4	CNC Console Troubleshooting in Non OCI Deployment	
4.1	Unable to display the release version of the NF at CNC Console banner	1
4.2	Unable to reach CNC Console Core IP or port directly	1
4.3	Admin user created under CNC Console realm is unable to access CNC Console IAM	1
4.4	CNC Console returns 403 error during NF Configuration	2
4.5	CNC Console returns 500 - Internal Server Error	2
4.6	CNC Console IAM is accessible, but CNC Console Core is not accessible	2
4.7	CNC Console IAM admin password configured through Kubectl secret is not reflected	3
4.8	Access Error in CNC Console Core GUI	3
4.9	Changing the CNC Console IAM admin password	3
4.10	Unable to access Kibana	3
4.11	CNC Console installation failure while installing using cnDBTier	4
4.12	CNC Console IAM kc pod fails while ASM is enabled	4

4.13	Unable to Access CNC Console GUI when ASM is Enabled	4
4.14	CNC Console Core GUI does not get loaded after logging in	4
4.15	CNC Console is not supporting ASM with mTLS disabled configuration	5
4.16	Pods not coming up in an ASM enabled CNC Console deployment in istio injected namespace	6
4.17	Failed to allocate IP for CNC Console IAM Ingress Gateway	7
4.18	Unable to Create required tables in CNC Console IAM DB	7
4.19	Resolve CNC Console Validation hook error	8
4.20	How to Reset CNC Console IAM Admin Password	9
4.21	Does CNC Console support Command Line Interface (CLI)	10
4.22	Upgrade or Rollback Failure	10
4.23	CNC Console Upgrade Results IP in Pending state	11
4.24	CNC Console Upgrade Displays Port Already in Use Error	11
4.25	CNC Console Helm Test Fails	11
4.26	CNC Console Helm Test Fails with Service Account Error	12
4.27	Unable to integrate LDAP with Console deployed on ASM setup	12
4.28	CNC Console IAM GUI gives an error while accessing some resources under master realm	15
4.29	Unable to login to CNC Console Core when TLS version is v1.2 and Ciphers Other Than That of TLSv1.2 are Provided	15
4.30	Database Connectivity Failure When Instance Level Access Control is Enabled	16
4.31	403 Forbidden Error when Accessing NF or CS Resources With Instance Level Access Control Enabled	16

5 CNC Console Troubleshooting in OCI Deployment

5.1	CNC Console Deployment pods are not coming up	1
5.2	CNC Console Core GUI is not loading	2
5.3	Getting invalid redirect uri error while accessing CNC Console Core	2
5.4	LDAP Integration Issues	3
5.5	Issues in SAML Authentication	3
5.6	CNC Console Access when private LoadBalancer IP is assigned	3
5.7	OCI IAM Connectivity Failure when Instance Level Access Control is Enabled	5
5.8	403 Forbidden Error when Accessing NF Resources With Instance Level Access Control Enabled	5

6 CNC Console Alerts

6.1	CNC Console IAM Alerts	1
6.1.1	CncclamTotalIngressTrafficRateAboveMinorThreshold	1
6.1.2	CncclamTotalIngressTrafficRateAboveMajorThreshold	2
6.1.3	CncclamTotalIngressTrafficRateAboveCriticalThreshold	3
6.1.4	CncclamMemoryUsageCrossedMinorThreshold	4

6.1.5	CnccclamMemoryUsageCrossedMajorThreshold	4
6.1.6	CnccclamMemoryUsageCrossedCriticalThreshold	5
6.1.7	CnccclamTransactionErrorRateAbove0.1Percent	5
6.1.8	CnccclamTransactionErrorRateAbove1Percent	6
6.1.9	CnccclamTransactionErrorRateAbove10Percent	6
6.1.10	CnccclamTransactionErrorRateAbove25Percent	7
6.1.11	CnccclamTransactionErrorRateAbove50Percent	7
6.1.12	CnccclamIngressGatewayServiceDown	8
6.1.13	CnccclamFailedLogin	9
6.1.14	AdminUserCreation	9
6.1.15	CnccclamAccessTokenFailure	10
6.2	CNC Console Core Alerts	10
6.2.1	CnccCoreTotalIngressTrafficRateAboveMinorThreshold	11
6.2.2	CnccCoreTotalIngressTrafficRateAboveMajorThreshold	11
6.2.3	CnccCoreTotalIngressTrafficRateAboveCriticalThreshold	12
6.2.4	CnccCoreMemoryUsageCrossedMinorThreshold	13
6.2.5	CnccCoreMemoryUsageCrossedMajorThreshold	13
6.2.6	CnccCoreMemoryUsageCrossedCriticalThreshold	14
6.2.7	CnccCoreTransactionErrorRateAbove0.1Percent	15
6.2.8	CnccCoreTransactionErrorRateAbove1Percent	15
6.2.9	CnccCoreTransactionErrorRateAbove10Percent	16
6.2.10	CnccCoreTransactionErrorRateAbove25Percent	16
6.2.11	CnccCoreTransactionErrorRateAbove50Percent	17
6.2.12	CnccCoreIngressGatewayServiceDown	17
6.2.13	CnccCoreFailedLogin	18
6.2.14	CnccCoreUnauthorizedAccess	18
6.2.15	CnccCoreAccessTokenFailure	19
6.3	CNC Console Alerts on OCI	20
6.3.1	CnccCoreTotalIngressTrafficRateAboveMinorThreshold	20
6.3.2	CnccCoreTotalIngressTrafficRateAboveMajorThreshold	20
6.3.3	CnccCoreTotalIngressTrafficRateAboveCriticalThreshold	21
6.3.4	CnccCoreMemoryUsageCrossedMinorThreshold	21
6.3.5	CnccCoreMemoryUsageCrossedMajorThreshold	21
6.3.6	CnccCoreMemoryUsageCrossedCriticalThreshold	22
6.3.7	CnccCoreTransactionErrorRateAbovePointOnePercent	22
6.3.8	CnccCoreTransactionErrorRateAboveOnePercent	23
6.3.9	CnccCoreTransactionErrorRateAboveTenPercent	23
6.3.10	CnccCoreTransactionErrorRateAboveTwentyFivePercent	23
6.3.11	CnccCoreTransactionErrorRateAboveFiftyPercent	24
6.3.12	CnccCoreUnauthorizedAccess	24

My Oracle Support

My Oracle Support (<https://support.oracle.com>) is your initial point of contact for all product support and training needs. A representative at Customer Access Support can assist you with My Oracle Support registration.

Call the Customer Access Support main number at 1-800-223-1711 (toll-free in the US), or call the Oracle Support hotline for your local country from the list at <http://www.oracle.com/us/support/contact/index.html>. When calling, make the selections in the sequence shown below on the Support telephone menu:

- For Technical issues such as creating a new Service Request (SR), select **1**.
- For Non-technical issues such as registration or assistance with My Oracle Support, select **2**.
- For Hardware, Networking and Solaris Operating System Support, select **3**.

You are connected to a live agent who can assist you with My Oracle Support registration and opening a support ticket.

My Oracle Support is available 24 hours a day, 7 days a week, 365 days a year.

Acronyms

The following table provides information about the acronyms and terminologies used in the document:

Table Acronyms

Acronym	Definition
A-CNCC Core	Agent CNC Console is a CNCC Core instance which manages local NF(s) and local OCCNE common services(s). A-CNCC is managed by M-CNCC. A-CNCC contains A-CNCC Core Ingress Gateway. A-CNCC has no IAM component. A-CNCC is also known as A-CNCC Core or aCncc Core.
AD	Active Directory
ASM	Aspen Service Mesh
BSF	Oracle Communications Cloud Native Core, Binding Support Function
CAPIF	Common API Framework
cnDBTier	Oracle Communications Cloud Native Core, cnDBTier
CNC Console	Oracle Communications Cloud Native Configuration Console
CNE	Oracle Communications Cloud Native Core, Cloud Native Environment
CS	Common Service
CRUD Operations	CREATE, READ, UPDATE, DELETE
ECDSA	Elliptic Curve Digital Signature Algorithm
EIR	Equipment Identity Register
HTTPS	Hypertext Transfer Protocol Secure
GRR	Geo Replication Recovery
IAM	Identity Access Management
Instance	NF or CNE common service managed by either M-CNCC Core or A-CNCC Core.
KPI	Key Performance Indicator
LDAP	Lightweight Directory Access Protocol
LDAPS	Lightweight Directory Access Protocol (Over SSL)
M-CNCC	Manager CNC Console or mCncc is a CNC Console instance which manages multiple A-CNCC and local instances. Non OCI: M-CNCC has two components M-CNCC IAM and M-CNCC Core OCI: M-CNCC has only M-CNCC Core component. M-CNCC IAM is substituted with OCI IAM.
M-CNCC IAM	Manager CNC Console IAM or M-CNCC IAM (also known as mCncc Iam) is an IAM component of M-CNCC. M-CNCC IAM contains M-CNCC IAM Ingress Gateway and M-CNCC IAM back-end microservices.

Table (Cont.) Acronyms

Acronym	Definition
M-CNCC Core	Manager CNC Console Core or M-CNCC Core (also known as mCncc Core) is a core component of M-CNCC that provides GUI and API access portal for accessing NF and OCCNE common services. M-CNCC Core contains M-CNCC Core Ingress Gateway and M-CNCC Core back-end microservices.
M-CNCC Kubernetes cluster	Kubernetes cluster hosting M-CNCC
MC	Multi Cluster. In multi cluster, a single CNCC can manage NF instances that access different Kubernetes clusters.
MO	Managed Objects
MOS	My Oracle Support
mTLS	Mutual Transport Layer Security
NEF	Oracle Communications Cloud Native Core, Network Exposure Function
NRF	Oracle Communications Cloud Native Core, Network Repository Function
OCI	Oracle Cloud Infrastructure
OCNADD	Oracle Communications Network Analytics Data Director
OCNWDAF	Oracle Communications Networks Data Analytics Function
OCNF	Oracle Communications Network Function
OSDC	Oracle Software Delivery Cloud
OSO	Oracle Communications Operations Services Overlay
PROVGW	Provisioning Gateway
REST API	Representational State Transfer Application Programming Interface
RBAC	Role Based Access Control
SAML	Security Assertion Markup Language
SBA	Service Based Architecture
SBI	Service Based Interface
SCP	Oracle Communications Cloud Native Core, Service Communication Proxy
SEPP	Oracle Communications Cloud Native Core, Security Edge Protection Proxy
Site	Kubernetes Cluster
SSO	Single Sign On
TLS	Transport Layer Security
UDR	Oracle Communications Cloud Native Core, Unified Data Repository
UE	User Equipment
URI	Subscriber Location Function

What's New in This Guide

This section lists the documentation updates for Release 24.2.x in Oracle Communications Cloud Native Configuration Console Troubleshooting Guide.

Release 24.2.5 - F95825-06, July 2025

There are no updates in this release.

Release 24.2.4 - F95825-05, April 2025

There are no updates in this release.

Release 24.2.3 - F95825-04, April 2025

There are no updates in this release.

Release 24.2.2 - F95825-03, January 2025

There are no updates in this release.

Release 24.2.1 - F95825-02, October 2024

Updated the [Types of Logs](#) and [Examples of Logs](#) sections to check the M-CNCC IAM KC Audit event logs.

Release 24.2.0 - F95825-01, July 2024

- Added the details to troubleshoot the following scenarios in the [CNC Console Troubleshooting in Non OCI Deployment](#) section:
 - [Unable to login to CNC Console Core when TLS version is v1.2 and Ciphers Other Than That of TLSv1.2 are Provided](#)
 - [Database Connectivity Failure When Instance Level Access Control is Enabled](#)
 - [403 Forbidden Error when Accessing NF or CS Resources With Instance Level Access Control Enabled](#)
- Added or updated the details to troubleshoot the following scenarios in the [CNC Console Troubleshooting in OCI Deployment](#) section:
 - [CNC Console Deployment pods are not coming up](#)
 - [OCI IAM Connectivity Failure when Instance Level Access Control is Enabled](#)
 - [403 Forbidden Error when Accessing NF Resources With Instance Level Access Control Enabled](#)

1

Introduction

This document provides information about troubleshooting Oracle Communications Cloud Native Configuration Console (CNC Console).

1.1 Overview

CNC Console is a single screen solution to configure and manage Network Functions (NFs). The CNC Console has the following two modules:

- CNC Console Core: CNC Console Core acts as GUI or API portal for NFs and CNE common services. CNC Console Core module includes CNC Console and its integration with other Cloud Native Core network functions. The CNC Console provides user interface that can be used to configure parameters for the following CNC network functions:
 - Oracle Communications Cloud Native Core, Binding Support Function (BSF)
 - Oracle Communications Cloud Native Core, Service Communication Proxy (SCP)
 - Oracle Communications Cloud Native Core, Network Repository Function (NRF)
 - Oracle Communications Cloud Native Core, Converged Policy (Policy)
 - Oracle Communications Cloud Native Core, Security Edge Protection Proxy (SEPP)
 - Oracle Communications Cloud Native Core, Unified Data Repository (UDR)
 - Oracle Communications Cloud Native Core Network Slice Selection Function (NSSF)
 - CNE Common Services
 - Data Director (DD)
 - Oracle Communications Network Data Analytics Function (NWDAF)
 - Provisioning Gateway (PROVGW)
 - Oracle Communications Cloud Native Core, Certificate Management (OCCM)
- CNC Console Identity Access Management (CNCC IAM): CNCC IAM acts as local identity provider and broker for external identity provider. CNCC IAM module includes the required authentication and authorization procedures such as creating and assigning roles to users.

1.2 Reference

Following are the reference documents:

- *Oracle Communications Cloud Native Configuration Console Installation and Upgrade Guide*
- *Oracle Communications Cloud Native Core DBTier Installation and Upgrade Guide*
- *Oracle Communications Cloud Native Configuration Console User Guide*
- *Oracle Communication Cloud Native Core Data Collector Guide*

2

Logs

This chapter explains the process to retrieve the logs and status that can be used for effective troubleshooting.

2.1 Collecting Logs

This section describes the steps to collect logs from PODs and containers. Perform the following steps:

1. Run the following command to get the PODs details:

```
$ kubectl -n <namespace_name> get pods
```

2. Collect the logs from the specific pods or containers:

```
$ kubectl logs <podname> -n <namespace> -c <containername>
```

3. Store the log in a file using the following command:

```
$ kubectl logs <podname> -n <namespace> > <filename>
```

4. (Optional) You can also use the following commands for the log stream with file redirection starting with last 100 lines of log:

```
$ kubectl logs <podname> -n <namespace> -f --tail <number of lines> > <filename>
```

For more information on kubectl commands, see Kubernetes [website](#).

2.2 Log Formats

This section provides information about the log formats.

[Log4j JSON Format](#)

[CNCC Message Format](#)

Log4j JSON Format

Following is the log format in JSON:

```
{
  "thread": <threadName>,
  "level": <log_level>,
  "loggerName": <name_of_the_logging_class>,
  "message": <message>,
  "instant": <timestamp_in_miliseconds>,
  "messageTimestamp": <timestamp_in_readable_format>,
  "threadId": <threadId>,
```

```

"threadPriority": <threadPriority>,
"pod": <name_of_the_pod>,
"processId": <processId>,
"contextMap": <context_map>,
"ocLogId": <unique_trace_id_for_every_request>,
"instanceType": <instanceType>,
"ingressTxId": <IngressTransactionId>
}

```

Table 2-1 Log Details

Name	Description	Example
thread	Name of the thread.	"thread": "reactor-http-epoll-1"
level	Level of the log. It can be: Log level (INFO, WARN, DEBUG, TRACE)	"level": "INFO"
loggerName	Name of the class that generated the log.	"loggerName": "ocpm.cne.gateway.cncc.GatewayApplication"
messageTimestamp	Time represented in human readable format and in UTC. Format is <i>date:yyyy-MM-dd'T'HH:mm:ss.SSSZ</i> EFK friendly and also follows Oracle Standards.	"messageTimestamp": 2020-07-04'T'12:00:40.702Z
message	Information about the event.	"message": "Started Application....." By default, all messages are in simple string except Audit Log , Security Log which are represented in CNC Console Message Format..
instant	The Date and Time the event occurred in epoch second and nano seconds.	"instant": { "epochSecond": 1590045388, "nanoOfSecond": 339789000}
processId	Linux process Identifier (for a multi-process host).	Linux process Identifier (for a multi-process host).
threadId	Id of the thread.	"threadId": "43"
threadPriority	Priority assigned to the thread	"threadPriority": 5
pod	Name of the pods where the log is generated	"cncc-mcore-ingress-gateway-77df795fb5-wv2sb"
contextMap	It holds information added to threadContext.	"contextMap": { "hostname": "cncc-mcore-ingress-gateway-77df795fb5-wv2sb", "ingressTxId": "ingress-tx-1460885598"}
ocLogId	It contains the trace id that is uniquely generated for every request of the format "<timestamp(in milliseconds)>_<thread Id>_<POD name>"	It contains the trace id that is uniquely generated for every request of the format "<timestamp (in milliseconds)>_<thread Id>_<POD name>"
instanceType	Static tag which implies that instance type is production	"instanceType": "prod"
ingressTxId	It contains id of the format "ingress-tx-<Random no>" to track every transaction	"ingressTxId": ingress-tx-1904660570

CNC Console Message Format

Table 2-2 CNC Console Message Format

Name	Description	Example	Possible Values
logType	Indicates whether it is Security Log or Audit Log .	logType=AUDIT	AUDIT SECURITY
type	Indicates nature or action of the log.	type=REQUEST	For Security Log: REQUEST, RESPONSE For Audit Log: LOGIN, ACCESS_RESOURCE, ACCESS_RESOURCE_ERROR, LOGOUT
resourceType	Indicates what is the resource being requested for.	resourceType=SCP	CM_SERVICE (For default route) CNC Console (For User Login Activity) SCP UDR NRF PCF (all CNC Console supported NFs)
userId	Id of the user who triggered request or action.	userId=3314f54f-08bf-489d-b395-27bf56da1262	NA
username	Name of the user	username= "user1"	NA
status	HTTP status of the response.	status=200 OK	NA
operationType	HTTP method of the request.	operationType=GET	NA
scheme	Indicates the scheme of the request.	scheme=http	NA
remoteAddress	The remote address that is associated with the request. It also means the remote address to where this request is connected when available.	remoteAddress=/192.168.219.64:53587	NA

Table 2-2 (Cont.) CNC Console Message Format

Name	Description	Example	Possible Values
localAddress	The local address that is associated with the request. It also means the local address to where this request is connected when available.	localAddress=cncc-mcore-ingress-gateway.cncc.svc.cluster.local/<unresolved>:30075	NA
resourcePath	Request URI	resourcePath=/soothsayer/v1/canaryrelease/	NA
queryParams	Query parameters associated with request.	queryParams={form_id=9, page=1, view_id=78}	NA
headers	Headers associated with request or response.	headers={Accept=/*/*, X-Requested-With=XMLHttpRequest, User-Agent=Mozilla/5.0 (Windows NT 10.0; WOW64; rv:68.0) Gecko/20100101 Firefox/68.0, Connection=keep-alive, Host=cncc-core-ingress-gateway.cncc.svc.cluster.local:30075, Accept-Language=en-US,en;q=0.5, Accept-Encoding=gzip, deflate, DNT=1, Content-Type=application/json; charset=utf-8}	NA
payload	Payload or Data associated with request or response.	payload=[{"serviceName":"n5g-eir-eic","canaryReleaseFlag":true,"apiFullVersion":"2.0.0","canaryTraffic":5}]	NA
authenticationType	This indicates whether user is requesting resource logged in using CNC Console or directly accessing through postman or curl.	authenticationType=OAUTH	OAUTH -> User is logged in through CNC Console application and accessing resource. JWT -> User is accessing resource directly through postman or curl.

2.3 Log Levels

Logs register system events along with their date and time of occurrence. They also provide important details about a chain of events that could have led to an error or problem.

A log level helps in defining the severity level of a log message. For CNC Console, the log level of a microservice can be set to any one of the following valid values:

- **TRACE:** A log level that describes events, as a step by step execution of code. This can be ignored during the standard operation, but may be useful during extended debugging sessions.
- **DEBUG:** A log level used for events during software debugging when more granular information is needed.
- **INFO:** A standard log level indicating that something has happened, an application has entered a certain state, etc.
- **WARN:** A log level indicates that something unexpected has happened in the application, a problem, or a situation that might disturb one of the processes. But this does not mean that the application has failed. The WARN level should be used in situations that are unexpected, but the code can continue to work.
- **ERROR:** A log level that should be used when an application hits an issue preventing one or more functionalities from functioning.

Using this information, the logs can be filtered based on the system requirements. For instance, if you want to filter the critical information about your system from the informational log messages, set a filter to view messages with only WARN log level in Kibana.

2.4 Types of Logs

The CNC Console logs can be categorized into following types:

- Regular logs
- Audit logs
- Security logs

Regular logs

These logs contain error messages, warnings, or other events written within the application that provide logical, high level information about the application and ongoing events.

Example:

```
{ "level": "INFO", "message": "Started GatewayApplication in 10.748 seconds  
(JVM running for 12.825)"}  
{ "level": "INFO", "message": "Creating plain httpClient"}  
{ "level": "INFO", "message": "Creating plain restTemplate"}  
{ "level": "ERROR", "message": "Can't get cfgs of topic  
public.dynamic.datamodel, exception is:\n  
javax.ws.rs.ProcessingException: java.net.ConnectException: Connection  
refused (Connection  
        refused)"} }
```

Audit Logs

Note

CNC Console IAM Audit logs are not applicable for OCI Deployment.

These logs contain user related information and the activity within the system.

The following events are logged in CNC Console Core:

- Log in: A user has logged in.
- Access Resource: A user is accessing a particular NF resource.
- Access Resource Error: A user is denied from accessing a particular NF resource.
- Logout: A user has logged out.

Note

The user can find the CNC Console Core User Activity logs as part of *cncc-core-ingress-gateway* and are represented in CNC Console message format.

The following events are logged in CNC Console IAM:

- Login events
- Log in: An admin user has logged in.
- Register: An admin user has registered.
- Logout: An admin user has logged out.
- Code to Token: An application or a client has exchanged a code for a token.
- Refresh Token: An application or a client has refreshed a token.

Account events

- Update Email: The email address for an account has changed.
- Update Profile: The profile for an account has changed.
- Send Password Reset: A password reset email has been sent.
- Update Password: The password for an account has changed.

Note

The user can find the CNC Console IAM User Activity logs as part of *cncc-iam-0*, represented in Keycloak format. These events are provided by keycloak and documented under [Keycloak Auditing End Events](#).

Logging Error Logs are recorded by keycloak container as :

```
^[[0m^[[33m10:12:57,388 WARN [org.keycloak.events] (default
task-3) type=LOGIN_ERROR, realmId=master, clientId=security-admin-
console,
    userId=ef58d62e-a0a8-4f4e-bcc6-abccf917641c,
    ipAddress=192.168.203.108, error=invalid_user_credentials,
    auth_method=openid-connect, auth_type=code,
    redirect_uri=http://10.75.240.33:30085/cncc/auth/admin/master/
console/,
    code_id=3e6d822a-9e82-4660-bb01-a814f7ae8f97, username=admin,
    authSessionParentId=3e6d822a-9e82-4660-bb01-a814f7ae8f97,
    authSessionTabId=2ak6Xwal-28
```

Security Logs

① Note

M-CNCC IAM Security logs are not applicable for OCI Deployment.

The security logs contain the header, payload, method, scheme, URI information for all the requests and corresponding responses.

Disabling Security Logs

By default Security Log will be enabled for *M-CCNC IAM*, *M-CNCC Core*, and *A-CNCC Core*. You can disable this by setting *securityLogEnabled* flag to false in *custom values.yaml* file.

```
# CNC Console configuration
cncc:
  # Enable security logs for CNC Console
  securityLogEnabled: false
```

Header Information

At all the log levels, sensitive information like Cookies are masked.

① Note

The user can find the Security logs:

- For M-CNCC Core and A-CNCC Core, these are logged as part of *cncc-mcore-ingress-gateway* or *cncc-acore-ingress-gateway* and are represented in CNC Console message format.
- For M-CNCC IAM, these are logged as part of *cncc-iam-ingress-gateway* and are represented in CNCC message format.

Log Levels

① Note

M-CNCC IAM ingress-gateway default log levels are not applicable for OCI deployment.

Default log levels set for M-CNCC Core and A-CNCC Core:

```
ingress-gateway:
  log:
    level:
      cncc:
        root: WARN
```

```
audit: INFO
security: INFO
```

Default log levels set for M-CNCC IAM:

```
ingress-gateway:
log:
  level:
    cncc:
      root: WARN
      security: INFO
```

Updating M-CNCC IAM Kubernetes Cluster (KC) log level

Note

M-CNCC IAM KC logs levels are not applicable for OCI Deployment.

- By default the log level of M-CNCC IAM KC is set to **WARN**, **org.keycloak.events:DEBUG**
 - This means the root log-level is set to **WARN** and the org.keycloak.events package is set to **DEBUG**
- In the **level** label, set the log level. Following are the different options available to set the log level:
 - **Log level**
 - * TRACE
 - * DEBUG
 - * INFO
 - * WARN
 - * ERROR
 - * FATAL
 - **level: OFF**
No logs will appear
- Sample M-CNCC IAM KC log configuration:

```
kc:
  preferIpv6Stack:
    enabled: false
  log:
    level: WARN,org.keycloak.events:DEBUG
```

Supported Headers for Logging

Header	Header values (regex)
Content-Type	^application/x-www-form-urlencoded.*

Header	Header values (regex)
Accept	^application/json.*
	^application/problem+json.*
	^application/json.*
	^application/ld+json.*
	^application/xml.*
	^multipart/form-data.*

Role of supporting headers in CNC Console Audit and Security logs

- At INFO level, only those request and response that match the supporting headers and values are logged.
- At DEBUG level, no supporting headers used and all request and response are logged.
- At ERROR / WARN, no supporting headers used and only error or warnings are logged.

Note

Any failure in authorizing a request will always be logged irrespective of the supported header configuration.

2.5 Examples of Logs

This section lists the examples of audit and security logs.

[Examples of Audit Logs](#)

[Examples of Security Logs](#)

Examples of Audit Logs

CNC Console Core

Only message part of the JSON log is shown in the example.

- User successfully logging into CNC Console Core

```
logType=AUDIT, type=LOGIN, resourceType=CNCC,
userId=186f6f2a-ba6a-4812-8a18-b906a5f9e3f6, username=user,
operationType=GET, remoteAddress=/192.168.219.64:53587,
localAddress=cncc-core-ingress-gateway.cncc.svc.cluster.local/
<unresolved>:30075,
resourcePath=/login/oauth2/code/cncc-iam,
authenticationType=0AUTH
```

- User accessing SCP resource having SCP_READ role

```
logType=AUDIT, type=ACCESS_RESOURCE, resourceType=SCP,
userId=186f6f2a-ba6a-4812-8a18-b906a5f9e3f6, username=user,
operationType=GET, remoteAddress=/192.168.219.64:53587,
localAddress=cncc-core-ingress-gateway.cncc.svc.cluster.local/
```

```
<unresolved>:30075,
resourcePath=/soothsayer/v1/canaryrelease/,
authenticationType=0AUTH
```

- User updating(PATCH) SCP resource having SCP_WRITE role

```
logType=AUDIT, type=ACCESS_RESOURCE, resourceType=SCP,
userId=186f6f2a-ba6a-4812-8a18-b906a5f9e3f6, username=user,
operationType=PATCH, remoteAddress=/192.168.219.64:53587,
localAddress=cncc-core-ingress-gateway.cncc.svc.cluster.local/
<unresolved>:30075,
resourcePath=/soothsayer/v1/canaryrelease/n5g-eir-eic,
authenticationType=0AUTH
```

- User accessing NRF resource without having NRF_READ role

```
logType=AUDIT, type=ACCESS_RESOURCE_ERROR, resourceType=NRF,
userId=186f6f2a-ba6a-4812-8a18-b906a5f9e3f6, username=user,
status=403 FORBIDDEN, operationType=GET,
remoteAddress=/192.168.219.64:53587,
localAddress=cncc-core-ingress-gateway.cncc.svc.cluster.local/
<unresolved>:30075,
resourcePath=/nrf-configuration/v1/system-options,
authenticationType=0AUTH
```

- User successful logout

```
logType=AUDIT, type=LOGOUT, resourceType=CNCC,
userId=186f6f2a-ba6a-4812-8a18-b906a5f9e3f6, username=user,
operationType=POST, remoteAddress=/192.168.219.64:53587,
localAddress=cncc-core-ingress-gateway.cncc.svc.cluster.local/
<unresolved>:30075,
resourcePath=/logout, authenticationType=0AUTH
```

CNC Console IAM:

① Note

- The defined CNC Console IAM Audit log examples are not applicable for OCI Deployment.
- The CNC Console IAM Security log examples are not applicable for OCI Deployment.
- To see M CNCC-IAM KC Audit event logs, set the *org.keycloak.events* package log to DEBUG in the *custom_values.yaml*. Refer [Updating M-CNCC IAM KC loglevel](#) for log level configuration.

- Login Error when password entered was wrong

```
04:56:35,890 WARN [org.keycloak.events] (default task-22)
                                type=LOGIN_ERROR, realmId=master,
clientId=security-admin-console,
                                userId=d7cde46f-15e1-4ff8-a2cb-c5825e481438,
ipAddress=192.168.219.64,
                                error=invalid_user_credentials,
auth_method=openid-connect,
                                auth_type=code, redirect_uri=http://
10.75.225.28:31373/cncc/auth/admin/master/console/, code_id=5aca4960-
eecf-406b-a7eb-92e249c2beeb,
                                username=admin,
                                authSessionParentId=5aca4960-eecf-406b-
a7eb-92e249c2beeb,
                                authSessionTabId=8sruELA1Wws
```

- Login with correct credential

```
04:57:24,581 DEBUG [org.keycloak.events] (default task-22)
                                type=LOGIN, realmId=master,
clientId=security-admin-console,
                                userId=d7cde46f-15e1-4ff8-a2cb-c5825e481438,
ipAddress=192.168.219.64,
                                auth_method=openid-connect, auth_type=code,
redirect_uri=http://10.75.225.28:31373/cncc/auth/admin/master/console/,
consent=no_consent_required,
                                code_id=5aca4960-eecf-406b-
a7eb-92e249c2beeb, username=admin,
                                authSessionParentId=5aca4960-eecf-406b-
a7eb-92e249c2beeb,
                                authSessionTabId=8sruELA1Wws
```

- User created

```
04:58:41,804 DEBUG [org.keycloak.events] (default task-22)
                                operationType=CREATE, realmId=master,
                                clientId=819ce4a5-ddbd-4717-908f-
a204bdabc808,
                                userId=d7cde46f-15e1-4ff8-a2cb-c5825e481438,
ipAddress=192.168.219.64,
                                resourceType=USER,
                                resourcePath=users/070911f5-c397-42c1-b5a4-
cd92fa435a33
```

- Deleted user

```
05:00:08,226 DEBUG [org.keycloak.events] (default task-22)
                                operationType=DELETE, realmId=master,
                                clientId=819ce4a5-ddbd-4717-908f-
a204bdabc808,
                                userId=d7cde46f-15e1-4ff8-a2cb-c5825e481438,
ipAddress=192.168.219.64,
                                resourceType=USER,
```

- ```
e0d0974ab73d resourcePath=users/2b931bbb-7f97-4f04-9f75-
```
- Admin Role removed for a user
 

```
05:01:07,781 DEBUG [org.keycloak.events] (default task-22)
 operationType=DELETE, realmId=master,
 clientId=819ce4a5-ddbd-4717-908f-
a204bdabc808,
 userId=d7cde46f-15e1-4ff8-a2cb-c5825e481438,
 ipAddress=192.168.219.64,
 resourceType=REALM_ROLE_MAPPING,
 resourcePath=users/
08fc0058-133b-4288-9165-14c96c5dcd7a/role-mappings/realm
```
  - Admin Role added for a user
 

```
05:01:33,664 DEBUG [org.keycloak.events] (default task-27)
 operationType=CREATE, realmId=master,
 clientId=819ce4a5-ddbd-4717-908f-
a204bdabc808,
 userId=d7cde46f-15e1-4ff8-a2cb-c5825e481438,
 ipAddress=192.168.219.64,
 resourceType=REALM_ROLE_MAPPING,
 resourcePath=users/
08fc0058-133b-4288-9165-14c96c5dcd7a/role-mappings/realm
```
  - Realm setting update
 

```
05:02:29,222 DEBUG [org.keycloak.events] (default task-26)
 operationType=UPDATE, realmId=master,
 clientId=819ce4a5-ddbd-4717-908f-
a204bdabc808,
 userId=d7cde46f-15e1-4ff8-a2cb-c5825e481438,
 ipAddress=192.168.219.64,
 resourceType=REALM, resourcePath=null
```
  - Logout all session on keycloak
 

```
05:05:02,383 DEBUG [org.keycloak.events] (default task-29)
 operationType=ACTION, realmId=master,
 clientId=819ce4a5-ddbd-4717-908f-
a204bdabc808,
 userId=d7cde46f-15e1-4ff8-a2cb-c5825e481438,
 ipAddress=192.168.219.64,
 resourceType=REALM, resourcePath=logout-all
```

### Examples of Security Logs

Representation for IAM and Core are same as these logs are part of ingress-gateway. Only message part of the JSON log is shown in the example.

CNC Console Core

- SCP request

```
logType=SECURITY, type=REQUEST, resourceType=SCP,
 userId=3314f54f-08bf-489d-
b395-27bf56da1262, username=user,
 operationType=GET, scheme=http,
 remoteAddress=/192.168.219.64:53587,
 localAddress=cncc-core-ingress-
gateway.cncc.svc.cluster.local/<unresolved>:30075,
 resourcePath=/soothsayer/v1/
canaryrelease/, queryParams={},
 headers={Accept=*/, X-Requested-
With=XMLHttpRequest,
 User-Agent=Mozilla/5.0 (Windows NT
10.0; WOW64; rv:68.0)
 Gecko/20100101 Firefox/68.0,
Connection=keep-alive,
 Host=cncc-core-ingress-
gateway.cncc.svc.cluster.local:30075,
 Accept-Language=en-US,en;q=0.5, Accept-
Encoding=gzip, deflate,
 DNT=1, Content-Type=application/json;
charset=utf-8},
 payload={}, authenticationType=OAUTH
```

- SCP response

```
logType=SECURITY, type=RESPONSE, resourceType=SCP,
 userId=3314f54f-08bf-489d-
b395-27bf56da1262, username=user,
 status=200 OK, operationType=GET,
 scheme=http,
 resourcePath=/soothsayer/v1/
canaryrelease/,
 headers={transfer-encoding=chunked,
Connection=keep-alive,
 Transfer-Encoding=chunked, Content-
Type=application/json,
 Date=Sat, 04 Jul 2020 11:58:20 GMT},
 payload=[{"serviceName":"n5g-eir-
eic", "canaryReleaseFlag":true, "apiFullVersion":"2.0.0", "canaryTraffic":5},
{"serviceName":"namf-
comm", "canaryReleaseFlag":true, "apiFullVersion":"2.0.0", "canaryTraffic":5},
{"serviceName":"namf-
evts", "canaryReleaseFlag":true, "apiFullVersion":"2.0.0", "canaryTraffic":5},
{"serviceName":"namf-
loc", "canaryReleaseFlag":true, "apiFullVersion":"2.0.0", "canaryTraffic":5},
{"serviceName":"namf-
mt", "canaryReleaseFlag":true, "apiFullVersion":"2.0.0", "canaryTraffic":5},
{"serviceName":"nausf-
auth", "canaryReleaseFlag":true, "apiFullVersion":"2.0.0", "canaryTraffic":5},
{"serviceName":"nausf-
sorprotection", "canaryReleaseFlag":true, "apiFullVersion":"2.0.0", "canaryTra
ffic":5}],
 authenticationType=OAUTH
```

## CNC Console IAM

The logs for IAM Ingress Gateway contain the username and user ID for all actions performed by CNCC-IAM admin users post-login, alongside other relevant information.

- Request

```
logType=SECURITY, type=REQUEST, userId=2811c05e-
bc84-4597-8014-3a88ef7535c2, username=admin, operationType=GET,
scheme=http, remoteAddress=/10.233.118.0:52597, localAddress=/
10.233.80.179:8081, resourcePath=/cncc/auth/admin/realms/master/users/
0931c7a1-34a6-45f1-9db5-5cd8a043fefb,
queryParams={userProfileMetadata=true}, headers={Connection=keep-alive,
User-Agent=Mozilla/5.0 (Macintosh; Intel Mac OS X 10_15_7) AppleWebKit/
537.36 (KHTML, like Gecko) Chrome/131.0.0.0 Safari/537.36,
uidToken=07338817-d0ac-4b18-948d-e3d5c0c91879, Host=10.121.42.53, Accept-
Encoding=gzip, deflate, svcName=cncc-iam-kc-http.amanp-ns.svc.thrust2a,
ocLogId=1733063953903_110_cncc-iam-ingress-gateway-5f7d9b9d87-dt6vj,
accept=application/json, text/plain, */*, sbi-timer-publish-headers=false,
content-type=application/json, Accept-Language=en-GB,
en; q=0.9,
sbi-timer-feature=false}, payload={}, authenticationType=UNKNOWN",
"endOfBatch": false, "loggerFqcn": "org-apache. logging.
10g4j.internal.DefaultLogBuilder", "threadId":112, "threadPriority":5,
"messageTimestamp":"2024-12-01T14:39:13.910+0000" ,
"processId": "1", "ingressTxId":"ingress-tx-1093411995", "pod": "cncc-iam-
ingress-gateway-5f7d9b9d87-dt6vj" ,
"ocLogId":"1733063953903_110_cncc-iam-ingress-gateway-5f7d9b9d87-dt6vi"
"instanceType":"prod" "RequestId": ''}
```

- Response

```
"message":" logType=SECURITY, type=RESPONSE, status=200 OK,
userId=2811c05e-bc84-4597-8014-3a88ef7535c2, username=admin,
operationType=GET, schemeshttp, resourcePath=/cncc/auth/admin/ realms/
master/clients/a6f486d4-0d0f-468d-a609-f655e9f1c492, headers={transfer-
encoding=chunked, content-length=772, Cache-Control=no-cache, Content-
Type=application/json;charset=UTF-8, Referrer-Policy=no-referrer, Strict-
Transport-Security=max-age=31536000; includeSubDomains, X-Content-Type-
Options=nosniff, X-Frame-Options=SAMEORIGIN, X-XSS-Protection=1;
mode=block, NettyLatency=1733064487125, RequestMethod=GET}, payload=
{"id":"a6f486d4-0d0f-468d-a609-f655e9f1c492", "clientId":"cncc-
realm", "name":"cncc Realm" ,
"surrogateAuthRequired": false, "enabled": true,
"alwaysDisplayInConsole": false, "clientAuthenticatorType":"client-
secret", "redirectUri": [1, "webOrigins": [1, "notBefore":0,
"beareronly": true, "consentRequired": false, "standardF
lowEnabled": true, "implicitFlowEnabled": false,
"directAccessGrantsEnabled": false, "serviceAccountsEnabled": false,
"publicClient": false, "frontchannelLogout": false, "attributes":
{}}, "authenticationFlowBindingOverrides": {}, "fullScopeAllowed": true,
"nodeReRegistrationTimeout":0, "defaultClientScopes": ["web-
origins", "roles", "profile", "email"], "optionalClientScopes":
["address", "phone", "offline_access", "microprofile-jwt"],
"access":{"view": true, "configure": true, "manage": true}},
authenticationType=UNKNOWN", "endofBatch": false, "loggerFqcn": "org-
```

```

apache. logging. log4j. internal.DefaultLogBuilder", "threadId":122,
"threadPriority":5, "messageTimestamp": "2024-12-01T14:48:07.152+0000",
"processId": "1" ,
"ingressTxId" : "ingress-tx-577080018", "pod": "cncc-iam-ingress-
gateway-5f7d9b9d87-dt6vj", "ocLogId" : "", "instanceType": "prod" ,
"RequestId" : ""}

```

## 2.6 Configuring Security Logs

This section provides the details about configuring security logs.

### Setting at Log Level

By default, Security Log is set to the "INFO" level for both CNC Console Core and CNC Console IAM. You can change the log level by setting `log.level.cncc.security` to the required level in core and iam values.yaml file.

#### values.yaml

```

#Set the root log level
log:
 level:
 root: WARN
 ingress: INFO
 oauth: INFO
 cncc:
 security: INFO

```

### Disabling Security Log

By default, the Security Log is enabled for both CNCC Core and CNCC IAM. You can disable this by setting `securityLogEnabled` flag to false in core and iam values.yaml file.

#### values.yaml

```

CNCC configuration
cncc:
 enabled: false
 enablehttp1: false
 securityLogEnabled: false

```

## 2.6.1 Accessing logs

This section gives information about how to access the logs.

### 2.6.1.1 Accessing Logs in Non OCI Deployment

The CNC Console application logs can be accessed in following ways:

1. Run the following command to view logs of a CNC Console application pod:

```
kubectl logs -f -n <cncc_namespace> <pod_name> -c <container_name>
```

Example:

CNC Console Core:

```
$ kubectl logs -f -n cncc cncc-mcore-ingress-gateway-77df795fb5-wv2sb -c ingress-gateway (Security & Audit Log)
```

CNC Console IAM:

```
$ kubectl logs -f -n cncc cncc-iam-ingress-gateway-77df795fb5-wv2sb -c ingress-gateway (Security Log)
```

```
$ kubectl logs -f -n cncc cncc-iam-0 (Audit Log)
```

2. CNC Console uses cloud native supported logging framework to view the logs.

Example : Elasticsearch, Fluentd, and Kibana (EFK) can be used here with CNC Console to view the logs as follows:


Figure 2-1 Log View



## 2.6.1.2 Accessing logs in OCI Deployment


1. Viewing logs for OCI IAM in OCI Console GUI:  
See the [Generate Identity and Access Management Reports from Oracle Cloud Infrastructure Audit](#) document to view OCI IAM logs.
2. Viewing logs for M-CNCC Core and A-CNCC Core in OCI Console GUI:
  - a. Log in to OCI Console GUI and search for **Log Explorer** or Click the Hamburger menu, click **Observability and Management**, then click **Log Explorer** in **Logging Analytics** section. This will open the Log Explorer page.

Figure 2-2 Log Explorer




- b. On the Log Explorer page, click **Kubernetes Container Generic logs**.

Figure 2-3 Kubernetes Container Generic logs




- c. After clicking the **Kubernetes Container Generic Logs** link, logs will be visible.

Figure 2-4 View Logs




- d. You can filter the logs by the container by clicking **Add to search**. Similarly other log source fields can also be added to filter logs.

Figure 2-5 Filter the logs by the container



- e. Filter logs based on the logType regex pattern for security and audit logs. Similarly required regex patterns can be used to filter the logs.

Figure 2-6 Regex Patterns for Filtering Logs



**Note**

For more details, see the Explore Logs section in the [Oracle Cloud Infrastructure Logging Analytics Quick Start Guide](#).

## 2.6.2 Debugging using Logs

This section provides information to debug CNC Console using Logs.

**Table 2-3 CNCC Core Debugging through Logs**

| Scenario                      | Level | Logs to be searched                                     |
|-------------------------------|-------|---------------------------------------------------------|
| CNC Core Login                | INFO  | Login successful                                        |
| Session Timeout Value         | INFO  | Session timeout                                         |
| Validating user authorization | INFO  | User Authorization Details                              |
| Accessing a resource          | DEBUG | Mapping [Exchange: GET                                  |
| Updating a resource           | DEBUG | Mapping [Exchange: PATCH 'or'<br>Mapping [Exchange: PUT |
| Creating a new resource       | DEBUG | Mapping [Exchange: POST 'or'<br>Mapping [Exchange: PUT  |
| CNCC Core Logout              | INFO  | Logout successful                                       |

# 3

## Debug Tool

### Overview

#### **Note**

CNC Console IAM is not applicable for OCI.

The Debug Tools provides third-party troubleshooting tools for debugging the runtime issues for the lab environment. Following are the available tools:

- tcpdump
- ip
- netstat
- curl
- ping
- dig

#### **Note**

Debug Tool is only applicable for lab setup, and not recommended for production use.

#### **Note**

While testing in OCCNE environment, check the Kyverno policies and make sure to exclude the namespace in the disallow-capabilities.

### Prerequisites

This section explains the prerequisites for using debug tool.

- For CNE 23.2.0 and later versions, follow [step a](#) of Configuration in CNE.
- For CNE versions prior to 23.2.0, follow [step b](#) of Configuration in CNE.

#### **1. Configuration in CNE**

The following configurations must be performed in the Bastion Host.

- a. When CNC Console is installed on CNE version 23.2.0 or above

**Note**

- You need admin privileges to edit or patch the clusterpolicies that are mentioned in following steps.
- In CNE v23.2.0 onwards, kyverno policy, disallow-capabilities does not allow NET\_ADMIN and NET\_RAW capabilities required for debug tool.

**Adding Namespace to the Empty Resource**

If the current disallow-capabilities cluster policy has no namespace in it, for example:

```
$ kubectl get clusterpolicies disallow-capabilities -oyaml
```

Sample output

```
apiVersion: kyverno.io/v1
kind: ClusterPolicy
...
...
spec:
 rules:
 - exclude:
 resources: {}
```

Then, run the following command to add the namespace:

```
$ kubectl patch clusterpolicy disallow-capabilities --type=json \
 -p='[{"op": "add", "path": "/spec/rules/0/exclude/any/0/resources",
"value": {"namespaces":["<namespace>"]} }]'
```

Example:

```
$ kubectl patch clusterpolicy disallow-capabilities --type=json \
 -p='[{"op": "add", "path": "/spec/rules/0/exclude/any/0/resources",
"value": {"namespaces":["cncc"]} }]'
```

Sample output

```
apiVersion: kyverno.io/v1
kind: ClusterPolicy
...
...
spec:
 rules:
 - exclude:
 resources:
 namespaces:
 - cncc
```

To remove the namespace, run the following:

```
$ kubectl patch clusterpolicy disallow-capabilities --type=json \
 -p='[{"op": "replace", "path": "/spec/rules/0/exclude/any/0/
resources", "value": {} }]'
```

Sample output

```
apiVersion: kyverno.io/v1
kind: ClusterPolicy
...
...
spec:
 rules:
 - exclude:
 resources: {}
```

### Adding a Namespace to the Existing Namespace List

If the current disallow-capabilities cluster policy has already namespaces added in it, for example:

```
$ kubectl get clusterpolicies disallow-capabilities -oyaml
```

Output:

```
apiVersion: kyverno.io/v1
kind: ClusterPolicy
...
...
spec:
 rules:
 - exclude:
 resources:
 namespaces:
 - namespace1
 - namespace2
 - namespace3
```

Then, run the following command to add your namespace:

```
$ kubectl patch clusterpolicy disallow-capabilities --type=json \
 -p='[{"op": "add", "path": "/spec/rules/0/exclude/any/0/resources/
namespaces/-", "value": "<namespace>" }]'
```

Example:

```
$ kubectl patch clusterpolicy disallow-capabilities --type=json \
 -p='[{"op": "add", "path": "/spec/rules/0/exclude/any/0/resources/
namespaces/-", "value": "cncc" }]'
```

Sample Output:

```
apiVersion: kyverno.io/v1
kind: ClusterPolicy
...
...
spec:
 rules:
 - exclude:
 resources:
 namespaces:
 - namespace1
 - namespace2
 - namespace3
 - cncc
```

To remove the namespace, run the following command:

```
$ kubectl patch clusterpolicy disallow-capabilities --type=json \
-p='[{"op": "remove", "path": "/spec/rules/0/exclude/any/0/resources/
namespaces/<index>"}]'
```

Example:

```
$ kubectl patch clusterpolicy disallow-capabilities --type=json \
-p='[{"op": "remove", "path": "/spec/rules/0/exclude/any/0/resources/
namespaces/3"}]'
```

Output:

```
apiVersion: kyverno.io/v1
kind: ClusterPolicy
...
...
spec:
 rules:
 - exclude:
 resources:
 namespaces:
 - namespace1
 - namespace2
 - namespace3
```

**b. Configurations in CNE Versions Prior to 23.2.0**

The following configurations must be performed in the Bastion Host.

**Note**

These steps are needed only when you have PSP admission controller enabled in your kubernetes environment.

## PodSecurityPolicy (PSP) Creation

- i. Log in to the Bastion Host.
- ii. Create a new PSP by running the following command. The parameters *readOnlyRootFilesystem*, *allowPrivilegeEscalation*, *allowedCapabilities* are needed by debug container.

### Note

Other parameters are mandatory for PSP creation and can be customized as per the CNE environment. Default values are recommended.

## PodSecurityPolicy

```
kubectl apply -f - <<EOF
apiVersion: policy/v1beta1
kind: PodSecurityPolicy
metadata:
 name: debug-tool-psp
spec:
 readOnlyRootFilesystem: false
 allowPrivilegeEscalation: true
 allowedCapabilities:
 - NET_ADMIN
 - NET_RAW
 fsGroup:
 ranges:
 - max: 65535
 min: 1
 rule: MustRunAs
 runAsUser:
 rule: MustRunAsNonRoot
 seLinux:
 rule: RunAsAny
 supplementalGroups:
 rule: RunAsAny
 volumes:
 - configMap
 - downwardAPI
 - emptyDir
 - persistentVolumeClaim
 - projected
 - secret
EOF
```

**Table 3-1 PodSecurityPolicy**

| Parameter  | Description                                                                   |
|------------|-------------------------------------------------------------------------------|
| apiVersion | APIVersion defines the versioned schema of this representation of an object.  |
| kind       | Kind is a string value representing the REST resource this object represents. |
| metadata   | Standard object's metadata.                                                   |

**Table 3-1 (Cont.) PodSecurityPolicy**

| Parameter                     | Description                                                                                                                             |
|-------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------|
| metadata.name                 | Name must be unique within a namespace.                                                                                                 |
| spec                          | spec defines the policy enforced.                                                                                                       |
| spec.readOnlyRootFilesystem   | Controls whether the containers run with a read-only root filesystem (that is no writable layer).                                       |
| spec.allowPrivilegeEscalation | Gates whether or not a user is allowed to set the security context of a container to allowPrivilegeEscalation=true.                     |
| spec.allowedCapabilities      | Provides a list of capabilities that are allowed to be added to a container.                                                            |
| spec.fsGroup                  | Controls the supplemental group applied to some volumes. RunAsAny allows any fsGroup ID to be specified.                                |
| spec.runAsUser                | Controls which user ID the containers are run with. RunAsAny allows any runAsUser to be specified.                                      |
| spec.seLinux                  | RunAsAny allows any seLinuxOptions to be specified.                                                                                     |
| spec.supplementalGroups       | Controls which group IDs containers add. RunAsAny allows any supplementalGroups to be specified.                                        |
| spec.volumes                  | Provides a list of allowed volume types. The allowable values correspond to the volume sources that are defined when creating a volume. |

**Role Creation**

Create a role for the PSP by running the following commands:

**Role**

```
kubectl apply -f - <<EOF
apiVersion: rbac.authorization.k8s.io/v1
kind: Role
metadata:
 name: debug-tool-role
 namespace: cncc
rules:
- apiGroups:
 - policy
 resources:
 - podsecuritypolicies
 verbs:
 - use
 resourceNames:
 - debug-tool-psp
EOF
```

**Table 3-2 Role**

| Parameter  | Description                                                                   |
|------------|-------------------------------------------------------------------------------|
| apiGroups  | APIGroups is the name of the APIGroup that contains the resources.            |
| apiVersion | APIVersion defines the versioned schema of this representation of an object.  |
| kind       | Kind is a string value representing the REST resource this object represents. |

**Table 3-2 (Cont.) Role**

| Parameter           | Description                                                                                                    |
|---------------------|----------------------------------------------------------------------------------------------------------------|
| metadata            | Standard object's metadata.                                                                                    |
| metadata.name       | Name must be unique within a namespace.                                                                        |
| metadata.namespace  | Namespace defines the space within which each name must be unique.                                             |
| rules               | Rules holds all the PolicyRules for this Role                                                                  |
| rules.resourceNames | ResourceNames is an optional white list of names that the rule applies to.                                     |
| rules.resources     | Resources is a list of resources this rule applies to.                                                         |
| rules.verbs         | Verbs is a list of Verbs that apply to ALL the ResourceKinds and AttributeRestrictions contained in this rule. |

**RoleBinding Creation**

Run the following command to attach the service account for your namespace with the role created for the tool PSP:

**RoleBinding**

```
kubectl apply -f - <<EOF
apiVersion: rbac.authorization.k8s.io/v1
kind: RoleBinding
metadata:
 name: debug-tool-rolebinding
 namespace: cncc
roleRef:
 apiGroup: rbac.authorization.k8s.io
 kind: Role
 name: debug-tool-role
subjects:
- kind: Group
 apiGroup: rbac.authorization.k8s.io
 name: system:serviceaccounts
EOF
```

**Table 3-3 RoleBinding**

| Parameter          | Description                                                                                     |
|--------------------|-------------------------------------------------------------------------------------------------|
| apiVersion         | APIVersion defines the versioned schema of this representation of an object.                    |
| kind               | Kind is a string value representing the REST resource this object represents.                   |
| metadata           | Standard object's metadata.                                                                     |
| metadata.name      | Name must be unique within a namespace.                                                         |
| metadata.namespace | Namespace defines the space within which each name must be unique.                              |
| roleRef            | RoleRef can reference a Role in the current namespace or a ClusterRole in the global namespace. |
| roleRef.apiGroup   | APIGroup is the group for the resource being referenced                                         |
| roleRef.kind       | Kind is the type of resource being referenced                                                   |
| roleRef.name       | Name is the name of resource being referenced                                                   |

**Table 3-3 (Cont.) RoleBinding**

| Parameter         | Description                                                                                                  |
|-------------------|--------------------------------------------------------------------------------------------------------------|
| subjects          | Subjects holds references to the objects the role applies to.                                                |
| subjects.kind     | Kind of object being referenced. Values defined by this API group are "User", "Group", and "ServiceAccount". |
| subjects.apiGroup | APIGroup holds the API group of the referenced subject.                                                      |
| subjects.name     | Name of the object being referenced.                                                                         |

### Configuration Changes in CNCC Helm Charts

To enable debug tools container, make changes to *occncc\_custom\_values\_<version>.yaml* file at Global level by setting *extraContainers: ENABLED*.

```
global:
 # Allowed Values: DISABLED, ENABLED
 # Preference is to set "resources" request and limit to same values to
 # avoid HPA issues.
 extraContainers: ENABLED
 debugToolContainerMemoryLimit: 4Gi
 extraContainersVolumesTpl: |
 - name: debug-tools-dir
 emptyDir:
 medium: Memory
 sizeLimit: {{ .Values.global.debugToolContainerMemoryLimit | quote }}
 extraContainersTpl: |
 - command:
 - /bin/sleep
 - infinity
 image: {{ .Values.global.dockerRegistry }}/ocncc/ocdebug-
tools:<debugtool_version>
 imagePullPolicy: IfNotPresent
 name: {{ printf "%s-tools-%s" (include "getprefix" .) (include
"getsuffix" .) | trunc 63 | trimPrefix "-" | trimSuffix "-" }}
 resources:
 limits:
 ephemeral-storage: "512Mi"
 cpu: "0.5"
 memory: {{ .Values.global.debugToolContainerMemoryLimit | quote }}
 requests:
 ephemeral-storage: "512Mi"
 cpu: "0.5"
 memory: {{ .Values.global.debugToolContainerMemoryLimit | quote }}
 securityContext:
 allowPrivilegeEscalation: true
 capabilities:
 drop:
 - ALL
 add:
 - NET_RAW
 - NET_ADMIN
 #runAsUser: <user-id>
 volumeMounts:
```

```
- mountPath: /tmp/tools
 name: debug-tools-dir
```

To enable debug tools at service level, make changes to *occncc\_custom\_values\_<version>.yaml* file at service level by setting *extraContainers: USE\_GLOBAL\_VALUE*

*occncc\_custom\_values\_<version>.yaml*

```
cncc-iam:
 kc:
 # Allowed Values: DISABLED, ENABLED, USE_GLOBAL_VALUE
 extraContainers: USE_GLOBAL_VALUE
```

```
ingress-gateway:
 # Allowed Values: DISABLED, ENABLED, USE_GLOBAL_VALUE
 extraContainers: USE_GLOBAL_VALUE
```

```
mcncc-core:
 cmservice:
 # Allowed Values: DISABLED, ENABLED, USE_GLOBAL_VALUE
 extraContainers: USE_GLOBAL_VALUE
```

```
ingress-gateway:
 # Allowed Values: DISABLED, ENABLED, USE_GLOBAL_VALUE
 extraContainers: USE_GLOBAL_VALUE
```

```
acncc-core:
 ingress-gateway:
 # Allowed Values: DISABLED, ENABLED, USE_GLOBAL_VALUE
 extraContainers: USE_GLOBAL_VALUE
```

#### Note

Debug Tool Container comes up with the default user ID - 7000. If the operator wants to override this default value, it can be done using the **runAsUser** field, otherwise the field can be skipped.

Default value: uid=7000(debugtool) gid=7000(debugtool)  
groups=7000(debugtool)

To override runAsUser add this line under securityContext in extraContainersTpl

```
runAsUser: <user-id>
```

## Configuration Options

**Table 3-4 Configuration Options**

| Parameter                                                          | Description                                                                                                                                                                                        |
|--------------------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| global.extraContainersTpl                                          | Describes the kubernetes container template for the debug-tool.                                                                                                                                    |
| global.debugToolContainerMemoryLimit                               | This field describes the memory size (request and limit) and emptyDir volume size for the Debug-tool container.                                                                                    |
| global.extraContainersTpl.command                                  | String array used for container command.                                                                                                                                                           |
| global.extraContainersTpl.image                                    | Docker image name                                                                                                                                                                                  |
| global.extraContainersTpl.imagePullPolicy                          | Image Pull Policy                                                                                                                                                                                  |
| global.extraContainersTpl.name                                     | Name of the container                                                                                                                                                                              |
| global.extraContainersTpl.resources                                | Compute Resources required by this container                                                                                                                                                       |
| global.extraContainersTpl.resources.limits                         | Limits describes the maximum amount of compute resources allowed                                                                                                                                   |
| global.extraContainersTpl.resources.requests                       | Requests describes the minimum amount of compute resources required                                                                                                                                |
| global.extraContainersTpl.resources.limits.cpu                     | CPU limits                                                                                                                                                                                         |
| global.extraContainersTpl.resources.limits.memory                  | Memory limits                                                                                                                                                                                      |
| global.extraContainersTpl.resources.limits.ephemeral-storage       | Ephemeral Storage limits                                                                                                                                                                           |
| global.extraContainersTpl.resources.requests.cpu                   | CPU requests                                                                                                                                                                                       |
| global.extraContainersTpl.resources.requests.memory                | Memory requests                                                                                                                                                                                    |
| global.extraContainersTpl.resources.requests.ephemeral-storage     | Ephemeral Storage requests                                                                                                                                                                         |
| global.extraContainersTpl.securityContext                          | Security options the container should run with.                                                                                                                                                    |
| global.extraContainersTpl.securityContext.allowPrivilegeEscalation | AllowPrivilegeEscalation controls whether a process can gain more privileges than its parent process. This boolean directly controls if the no_new_privs flag will be set on the container process |
| global.extraContainersTpl.securityContext.capabilities             | The capabilities to add or drop when running containers. Defaults to the default set of capabilities granted by the container runtime.                                                             |
| global.extraContainersTpl.securityContext.capabilities.drop        | Removed capabilities                                                                                                                                                                               |
| global.extraContainersTpl.securityContext.capabilities.add         | Added capabilities                                                                                                                                                                                 |
| global.extraContainersTpl.securityContext.runAsUser                | The UID to run the entrypoint of the container process.                                                                                                                                            |
| global.extraContainersTpl.volumeMounts.mountPath                   | The path where the emptyDir volume has to be mounted inside the container.                                                                                                                         |
| global.extraContainersTpl.volumeMounts.name                        | Name of the emptyDir volume.                                                                                                                                                                       |

## Debug Tool Volume Parameters

**Table 3-5 Debug Tool Volume Parameters**

| Parameter                                           | Description                                                           |
|-----------------------------------------------------|-----------------------------------------------------------------------|
| global.extraContainersVolumesTpl                    | Describes the kubernetes volume template for the debug-tool container |
| global.extraContainersVolumesTpl.name               | Name of the emptyDir volume.                                          |
| global.extraContainersVolumesTpl.emptyDir.sizeLimit | The size of the emptyDir volume.                                      |
| global.extraContainersVolumesTpl.emptyDir.medium    | Describes where emptyDir volumes are stored.                          |

## Debug Tool Usage

Following is the procedure to run Debug Tool:

1. Run the following command to retrieve the POD details:

```
$ kubectl get pods -n <k8s namespace>
```

Example:

```
kubectl get pod -n cncc
```

Sample Output:

| NAME                                        | READY | STATUS  | RESTARTS |
|---------------------------------------------|-------|---------|----------|
| AGE                                         |       |         |          |
| cncc-acore-ingress-gateway-764f7f5f77-qnr5p | 2/2   | Running | 0        |
| 19m                                         |       |         |          |
| cncc-iam-ingress-gateway-55987f7dc9-x5nt2   | 2/2   | Running | 0        |
| 147m                                        |       |         |          |
| cncc-iam-kc-0                               | 2/2   | Running | 0        |
| 147m                                        |       |         |          |
| cncc-mcore-cmservice-947cf4c89-76vq6        | 2/2   | Running | 0        |
| 19m                                         |       |         |          |
| cncc-mcore-ingress-gateway-764f7f5f77-qnr5p | 2/2   | Running | 0        |
| 19m                                         |       |         |          |

2. Run the following command to enter Debug Tools Container:

```
kubectl exec -it <pod name> -c <debug_container name> -n <namespace> bash
```

Example:

```
kubectl exec -it cncc-mcore-ingress-gateway-599d858867-x9pvz -c tools -n cncc bash
```

3. Run the debug tools:

```
bash -4.2$ <debug_tools>
```

Example:

```
bash -4.2$ tcpdump
```

4. Run the following command to copy output files from container to host:

```
$ kubectl cp -c <debug_container name> <pod name>:<file location in container> -n <namespace> <destination location>
```

Example:

```
$ kubectl cp -c tools -n cncc cncc-mcore-ingress-gateway-764f7f5f77-qnr5p:/tmp/capture.pcap /tmp/
```

### Steps to Enable Debug Tools Container

Debug tools container can be enabled or disabled for CNCC components by using `helm install` or `helm upgrade` command.

### CNC Console

Run the following command to enable or disable CNC Console IAM after updating `occncc_custom_values_<version>.yaml` file on a installed setup:

```
$ helm upgrade <release_name> -f ocncnc_custom_values_<version>.yaml <helm-repo> --version <helm_version>
```

Example:

```
$ helm upgrade cncc -f ocncnc_custom_values_24.2.3.yaml ocsfp_helm-repo/cncc --version 24.2.4
```

# 4

## CNC Console Troubleshooting in Non OCI Deployment

This section provides information to troubleshoot the common errors which can be encountered during the installation and upgrade of CNC Console.

### 4.1 Unable to display the release version of the NF at CNC Console banner

#### Unable to display the release version of the NF at CNC Console banner

**Problem:** CNC Console banner displays the release version of CNC Console, but not displaying the release version of the NF.

**Solution:**

- The “About” section and Application name displayed next to Oracle logo use the `envSystemName` and `envNFVersion` helm fields.
- The value set of `envSystemName` and `envNFVersion` combines to display the Application name (Application name = `envSystemName` + `envNFVersion`).
- CNC Console Core Custom values have `envSystemName` and `envNFVersion` mentioned in it, but these values can be overridden.

### 4.2 Unable to reach CNC Console Core IP or port directly

#### Unable to reach CNC Console Core IP or port directly

**Problem:** Unable to reach CNC Console Core IP or port directly. `redirect_uri` is inserted instead of directly accessing the CNC Console Core.

**Solution:** As per the design, CNC Console redirects requests to CNC Console IAM for authentication. On successful authentication, CNC Console IAM redirects the user back to CNC Console GUI.

### 4.3 Admin user created under CNC Console realm is unable to access CNC Console IAM

#### Admin user created under CNC Console realm is unable to access CNC Console IAM

**Problem:** The user with ‘Admin’ privileges is unable to access CNC Console IAM.

**Solution:** Users created under the `Cncc` realm have access only to CNC Console Core and not to CNC Console IAM. To access CNC Console IAM, create the admin user under the `Master` realm.

## 4.4 CNC Console returns 403 error during NF Configuration

### CNC Console returns 403 error during NF Configuration

**Problem:** CNCCConsole returns a 403 Error Code and error *"Forbidden. Data could not be saved"*.

**Error Code/Error Message:**  
403/Forbidden

**Solution:** Log into CNC Console IAM to check the roles of the user. The user must have <NF>\_READ and <NF>\_WRITE roles assigned to perform the write operation on any NF through the CNC Console.

## 4.5 CNC Console returns 500 - Internal Server Error

### CNC Console returns 500 - Internal Server Error

**Problem:** CNC Console returns a 500 Error Code while accessing NF Resource.

**Error Code/Error Message:**  
500/Internal Server Error

**Solution:** The internal server error occurs when the NF routes are not configured correctly. To resolve this error, ensure that correct routes for each NF are configured during deployment. You can provide routes in either of the IP/FQDN in the Instances section:

```
id: <Instance ID>
type: <NF type>
owner: <ID of cluster owning the Instance>
ip: <IP of NF deployment>
port: <Port of NF deployment>
```

## 4.6 CNC Console IAM is accessible, but CNC Console Core is not accessible

### CNC Console IAM is accessible, but CNC Console Core is not accessible

**Problem:** CNC Console IAM is accessible, but CNC Console Core is not accessible.

**Error Message:**

The ID Token contains invalid claims, which is a JWT validation error, indicating that the system clock on your server is off.

**Observation:** This issue occurs when Ingress Gateway is behind in time and when CNC Console IAM is ahead of time. For example, If IAM (node1) is ahead of time and Ingress Gateway (node2) is 5 minutes behind, the Ingress Gateway invalidates the received token and throws *"The ID Token contains invalid claims: {iat=2020-05-26T08:32:12Z}"* error.

**Solution:** To resolve the error, you must ensure that the same time is maintained in CNC Console IAM and Ingress Gateway when they run in the same instance or different NTP server instances.

## 4.7 CNC Console IAM admin password configured through Kubectl secret is not reflected

### CNC Console IAM admin password configured through Kubectl secret is not reflected

**Problem:**

CNC Console IAM admin password change through cncc-iam-secret is not working (Example: if configured cncc-iam-secret).

**Solution:** During the first installation, CNC Console IAM reads the password from the cncc-iam-secret and stores it in the database. So any further changes to the admin password must be done through the CNC Console IAM GUI.

## 4.8 Access Error in CNC Console Core GUI

### Access Error in CNC Console Core GUI

**Problem:**

Unable to access CNC Console Core GUI and an “Invalid redirect URI” error occurs.

**Observation:**

This error occurs when there is a mismatch between the Root URL provided in CNC Console IAM Admin Console and the URI through which you access the CNC Console Core GUI.

For example, In CNC Console IAM, the Root URL is mentioned as *http://cncc-core-ingress-gateway.cncc.svc.cluster.local:30075/* and if you are accessing the CNC Console Core GUI with IP and NodePort, that is, *http://10.75.xx.xx:30075/\** or vice-versa, you get “invalid redirect\_uri” error on CNC Console Core GUI.

**Solution:** To resolve this error, ensure that the Root URL provided in CNC Console IAM and the URI through which you access the CNC Console Core GUI are the same.

## 4.9 Changing the CNC Console IAM admin password

### Changing the CNC Console IAM admin password

**Problem:**

How to change the CNC Console IAM admin password using the REST API call.

**Solution:** Refer the following sections in CNC Console User Guide:

- Accessing NF Resources through Curl or Postman
- CNC Console IAM REST APIs

## 4.10 Unable to access Kibana

### Unable to access Kibana

**Problem:**

Kibana Common Service is not accessible

**Solution:** To resolve this issue, ensure that you are accessing Kibana through the correct path. The default access path to Kibana is through "/kibana". You can also access Kibana through the URL `<node-ip>:<node-port>/mycne-cluster/kibana`.

## 4.11 CNC Console installation failure while installing using cnDBTier

### CNC Console installation failure while installing using cnDBTier

**Problem:**

While installing CNC Console using cnDBTier, the `cncc-iam-kc` pod does not come up and goes into a crash state.

**Solution:** cnDBTier needs additional grants such as "REFERENCES, INDEX" due to the addition of db hook job.

## 4.12 CNC Console IAM kc pod fails while ASM is enabled

### CNC Console IAM kc pod fails while ASM is enabled

**Problem:**

While ASM is enabled, CNC Console IAM kc pod fails due to Readiness probe failure.

**Solution:** Check whether annotation `"sidecar.istio.io/rewriteAppHTTPProbers"` is enabled and set to true under `'nonIbStatefulSets'` in `custom_cncc-iam_values.yaml` during CNC Console IAM deployment.

## 4.13 Unable to Access CNC Console GUI when ASM is Enabled

### Unable to Access CNC Console GUI when ASM is Enabled

**Problem:**

Unable to access CNC Console GUI after installation as `cncc-iam-ingress-gateway` is listening on port 8080 instead of port 8081(ASM enabled).

**Solution:** After installing CNC Console, the `cncc-iam-ingress-gateway` is listening on port 8080 instead of port 8081 when ASM is enabled. To resolve this issue, configure the parameters in the `custom_cncc-iam_values.yaml` file as follows:

- Annotation: `sidecar.istio.io/rewriteAppHTTPProbers: "\"true\""`
- `serviceMeshCheck: true`
- Annotation: `sidecar.istio.io/inject: "true"`

## 4.14 CNC Console Core GUI does not get loaded after logging in

### CNC Console Core GUI does not get loaded after logging in

**Problem**

CNC Console Core microservices are up and running but CNC Console Core GUI does not get loaded after logging in.

**Solution**

CNC Console supports only single pod deployment, check the following configurations (must be set to 1).

```
ingress-gateway:
Number of Pods must always be available, even during a disruption.
minAvailable: 1
Min replicas to scale to maintain an average CPU utilization
minReplicas: 1
Max replicas to scale to maintain an average CPU utilization
maxReplicas: 1
```

#### ① Note

These are preset to 1 and these parameters are not exposed in custom values.

## 4.15 CNC Console is not supporting ASM with mTLS disabled configuration

### CNC Console is not supporting ASM with mTLS disabled configuration

#### Problem

When service mesh is enabled and mTLS is set either to disabled or to permissive with insecure HTTP connections, CNC Console Core microservice doesn't come up or CNC Console Core GUI takes time to load because some internal CSS or JS calls are still triggered with HTTPs.

#### Solution

1. Update `serviceMeshHttpsEnabled` to false in `custom-cncc-core_values.yaml` file to allow insecure HTTP connections.

```
#Mandatory: This parameter must be set to "true" when CNC Console is
deployed with the Service Mesh
serviceMeshCheck: true
If Service Mesh is deployed with TLS/MTLS disabled then set this flag to
false
serviceMeshHttpsEnabled: false
```

2. Add a PeerAuthentication rule stating mTLS is disabled for CNC Console namespace. For example,

```
kubectl apply -n <namespace> -f - <<EOF
apiVersion: security.istio.io/v1beta1
kind: PeerAuthentication
metadata:
 name: cnccpeer
spec:
 mtls:
 mode: DISABLE
EOF
```

```
#####
```

```
Example with cncc as namespace
#####
kubectl apply -n cncc -f - <<EOF
apiVersion: security.istio.io/v1beta1
kind: PeerAuthentication
metadata:
 name: cnccpeer
spec:
 mtls:
 mode: DISABLE
EOF
```

## 4.16 Pods not coming up in an ASM enabled CNC Console deployment in istio injected namespace

### Pods not coming up in an ASM enabled CNC Console deployment in istio injected namespace

#### Problem

CNC Console pods don't come up when sidecar injection is enabled and CNC Console is deployed in CNE, and the following error is seen:

```
job/cncc-iam-pre-install Error creating: pods "cncc-iam-pre-
install-" is forbidden: PodSecurityPolicy: unable to admit pod:
[spec.initContainers[0].securityContext.runAsNonRoot: Invalid value: false:
must be true spec.initContainers[0].securityContext: Invalid value:
[]int64{0}: group 0 must be in the ranges: [{1 65535}]
spec.initContainers[0].securityContext.capabilities.add: Invalid value:
"NET_ADMIN": capability may not be added
spec.initContainers[0].securityContext.capabilities.add: Invalid value:
"NET_RAW": capability may not be added
spec.initContainers[0].securityContext.runAsNonRoot: Invalid value: false:
must be true]
```

#### Solution

You must bind the ClusterRole "psp:privileged" to the current namespace:

```
kubectl apply -f - <<EOF
apiVersion: rbac.authorization.k8s.io/v1
kind: RoleBinding
metadata:
 name: "psp:<namespace>:cs-restricted"
 namespace: "<namespace>"
roleRef:
 kind: ClusterRole
 apiGroup: rbac.authorization.k8s.io
 name: "psp:privileged"
subjects:
- kind: Group
 apiGroup: rbac.authorization.k8s.io
```

```
name: "system:serviceaccounts"
EOF
```

## 4.17 Failed to allocate IP for CNC Console IAM Ingress Gateway

### Failed to allocate IP for CNC Console IAM Ingress Gateway

#### Problem

Installation of CNC Console IAM is successful but while checking CNC Console IAM service status, unable to assign the external IP for svc cncc-iam-ingress-gateway and received the following error: *Warning Allocation Failed 61s (x3 over 8m48s) metallb-controller Failed to allocate IP for "cncc/cncc-iam-ingress-gateway": no available IPs.*

#### Solution

Check if the annotations are missing from the cncc-iam-ingress-gateway service. Add the missing annotations, due to which the dynamic metalLBIPAllocation will work properly.

## 4.18 Unable to Create required tables in CNC Console IAM DB

### Unable to Create required tables in CNC Console IAM DB

#### Problem

Deployment needs two instances of CNC Console where only the first instance is deployed correctly. After installing the second instance of CNC Console in a different namespace, the pod "cncc-voice-iam-kc-0" repeatedly crashes

#### Observation

After analyzing the logs, it was found that during the preinstall checks, the hook pods did not create all the required tables in the DB. For example, in the first instance DB, all tables created, while in the second instance DB, there are only 43 tables created. The cbDBTier has a maximum table limit of 512. So, during the deployment of the second instance of CNC Console, the maximum table limit threshold has exceeded, and hence 43 tables were created.

Deployment needs two instances of CNC Console, first instance is deployed correctly.

After the installation of the second cncc-iam in a different namespace, the *pod cncc-voice-iam-kc-0* is crashed repeatedly. By analyzing the logs it seems that not all the tables has been created by the hook pods during the pre-install checks. In the first instance db we can see that there are all tables created while in the second instance we can see only 43 tables.

#### Solution

To resolve this issue, you must either increase the maximum table limit or clean up unwanted databases to bring table count within the threshold limits. For more information about configuring the table limits, see *Oracle Communications Cloud Native Core DBTier Installation and Upgrade Guide*.

Default limits in ndb:

MaxNoOfOrderedIndexes: 512

MaxNoOfTables: 512

NoOfFragmentLogFiles: 256

## 4.19 Resolve CNC Console Validation hook error

### Resolve CNC Console Validation hook error

#### Problem

Validation hook error occurs during CNC Console Core Deployment.

#### Solution

To resolve this issue, enable Helm Configuration Validation for CNC Console Deployment, applicable for M-CNCC Core and A-CNCC deployment.

Check the *cncc-acore-validation-hook* or *cncc-mcore-validation-hook* pod logs for the error codes. Make the required corrections in the *custom-cncc-core\_values.yaml* file and reinstall M-CNCC Core or A-CNCC. For more information about validation hook and error details, see "CNC Console Multi Cluster Deployment Helm Configuration Validation" section in *Oracle Communications Cloud Native Configuration Console Installation and Upgrade Guide*.

| Error Code | Error Message Format                                                                                     | Error Scenarios                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                           | Sample Error Messages                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
|------------|----------------------------------------------------------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| 1001       | Invalid value.<br>Resource:<br><Configuration Name>, ID: <ID>,<br>Attribute:<br><Attribute>. <More Info> | <ul style="list-style-type: none"> <li>Port should be Numeric</li> <li>Scheme should be either HTTP/HTTPS</li> <li>IDs should follow the alphanumeric pattern</li> <li>Max Limit should be satisfied for M-CNCC IAM, A-CNCC and Instance</li> <li>Max Length for Instance Id</li> <li>Max Length for Self Cncc Id</li> <li>CS instance must have one of these CS subtypes &lt;grafana, kibana, jaeger, prometheus, alertmanager&gt;</li> <li>Both ip and fqdn cannot be provided.</li> <li>Unsupported type</li> <li>InvalidConfig</li> <li>multicuster flag should be false in case of single-cluster deployment</li> <li>multicuster flag should be true in case of multi-cluster deployment</li> </ul> | <p>Invalid value. Resource: mCnccclam, ID: Cluster1, Attribute: Port. It should be numeric value.</p> <p>Invalid value. Resource: instance, ID: Cluster3 Cluster3-instance1, Attribute: Scheme. Allowed values are: [http, https].</p> <p>Invalid value. Resource: instance, ID: Cluster1-grafana##\$\$%, Attribute: id. Ids should be alphanumeric with hyphen allowed as special character.</p> <p>The count of mCnccclam exceeded max limit. Allowed Value:x. Actual Value: y</p> <p>Max limit exceeded. Allowed Value:x. Actual Value: y</p> <p>Invalid value. Resource: aCncc, ID: Cluster3, Attribute: N/A. Both ip and fqdn cannot be provided.</p> <p>Invalid value. Resource: isMultiClusterEnabled, ID:,Attribute: False.</p> <p>isMultiClusterEnabled is set as false, only single cluster configuration is allowed.</p> <p>Invalid value. Resource: isMultiClusterEnabled, ID:,Attribute: True.</p> <p>isMultiClusterEnabled is set as true, only multi cluster configuration is allowed.</p> |

| Error Code | Error Message Format                                                                                         | Error Scenarios                                                                                                                                                                          | Sample Error Messages                                                                                                                                                                                                                 |
|------------|--------------------------------------------------------------------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| 1002       | Duplicate value.<br>Resource:<br><Configuration Name>, ID: <ID>,<br>Attribute:<br><Attribute>. <More Info>   | <ul style="list-style-type: none"> <li>All A-CNCC IDs must be unique</li> <li>API prefix must be unique for all instances</li> <li>Owner(Cluster) must have unique CS subtype</li> </ul> | Duplicate value(s). Resource: aCncc, ID: [Cluster3], Attribute: id.                                                                                                                                                                   |
| 1003       | Invalid Reference.<br>Resource:<br><Configuration Name>, ID: <ID>,<br>Attribute:<br><Attribute>. <More Info> | <ul style="list-style-type: none"> <li>All the Instance owners must be referenced in M-CNCC IAM IDs or A-CNCC IDs</li> <li>M-CNCC IAM IDs and M-CNCC Core IDs must be same</li> </ul>    | Invalid Reference. Resource: instance, ID: Cluster5, Attribute: Owner. Not present in mCncc ids or aCncc ids.<br><br>Invalid Reference. Resource: instance, ID: N/A, Attribute: N/A. M-Cncc iam ids and M-Cncc Core ids do not match. |
| 1004       | Missing value.<br>Resource:<br><Configuration Name>, ID: <ID>,<br>Attribute:<br><Attribute>. <More Info>     | <ul style="list-style-type: none"> <li>Missing apiPrefix parameter for type CS</li> <li>Either of IP/FQDN should be present</li> </ul>                                                   | Missing value. Resource: instance, ID: Cluster4-grafana, Attribute: apiPrefix.<br><br>Missing value. Resource: instance, ID: Cluster3-PolicyInstance, Attribute: N/A. Either ip or fqdn is required.                                  |

## 4.20 How to Reset CNC Console IAM Admin Password

### How to Reset CNC Console IAM Admin Password

**Problem:** How to Reset CNC Console IAM Admin Password

**Solution:** To reset the CNC Console IAM admin password, perform the following procedure:

1. Run the following command to get into the mysql pod of cnDBTier:

```
k exec -it <mysql pod name> -n <namespace> bash
```

2. Run the following command to login to mysql:

```
mysql -h 127.0.0.1 -u <username> -p<password>
```

3. Run the following command to use the database that you used to deploy the CNC Console application:

```
use <database name>
```

4. Run the following command to find the admin user ID from the USER\_ENTITY table:

```
select * from USER_ENTITY
```

5. Run the following command to delete the admin user ID entry from CREDENTIAL table:

```
delete from CREDENTIAL where user_id = '<user-id>'
```

6. Run the following command to delete the admin user ID entry from ROLE\_MAPPING table:

```
delete from USER_ROLE_MAPPING where user_id = '<user-id>'
```

7. Run the following command to delete the admin user ID entry from USER\_ENTITY table:

```
delete from USER_ENTITY where ID = '<user-id>'
```

8. Run the following command to restart the IAM-KC-0 pod and login to CNC Console IAM using the password given in the cncc-iam secret:

```
Kubectl delete po <IAM-KC Pod> -n <namespace>
```

## 4.21 Does CNC Console support Command Line Interface (CLI)

### Does CNC Console support Command Line Interface (CLI)

**Problem:** Can NF APIs integrated with CNC Console be accessed through curl or postman.

**Solution** The NF configuration APIs can be accessed through CNC Console GUI or directly using postman or curl. CNC Console provides authentication and authorization in both ways. For more information, see "Generating Access Tokens and Accessing NF Resources" section in *Oracle Communications Cloud Native Configuration Console User Guide*.

## 4.22 Upgrade or Rollback Failure

### Upgrade or Rollback Failure

**Problem:** Upgrade or Rollback Failure

### Solution

When CNC Console upgrade or rollback fails, perform the following procedure:

1. Check the pre or post upgrade or rollback hook logs as applicable.
2. If the failure occurs, then check the cause of the failure from the logs by running the following command:

```
kubectl logs <pod name> -n <namespace>
```

3. After detecting the cause of failure, do the following:
  - For upgrade failure:
    - If the cause of upgrade failure is database or network connectivity issue, then resolve the issue and rerun the upgrade command.
    - If the upgrade failure occurs during the postupgrade phase, for example, post upgrade hook failure due to target release pod not moving to ready state, then perform a rollback.
  - For rollback failure: If the cause of rollback failure is database or network connectivity issue, then resolve the issue and rerun the rollback command.
4. If the issue persists, contact [My Oracle Support](#).

## 4.23 CNC Console Upgrade Results IP in Pending state

### CNC Console Upgrade Results IP in Pending state

**Problem:** CNC Console deployment using static IP is not allocated to the new mcore service during upgrade.

#### Solution

CNCC supports the single helm chart deployment for deploying all three components M-CNCC IAM, M-CNCC Core and A-CNCC Core.

Earlier CNCC IAM and CNCC Core were deployed independently, now with single helm chart all 3 components can be deployed using single helm install command.

Upgrade from two helm deployments to one helm deployment is supported but one of the helm deployment must be manually deleted.

CNCC IAM deployment can be upgraded which upgrades M-CNCC IAM and freshly install M-CNCC Core and A-CNCC Core services. User can manually delete CNCC Core deployment. For more information, see Upgrade and Rollback sections of *Oracle Communications Cloud Native Configuration Console Installation and Upgrade Guide*.

In case, if static LoadBalancer IP is used in existing deployment, after the upgrade, new mcore service IP will be shown as pending. IP will be allocated once the existing M-CNCC Core service is uninstalled.

## 4.24 CNC Console Upgrade Displays Port Already in Use Error

### CNC Console Upgrade Displays Port Already in Use Error

**Problem:** CNC Console deployment using static node port throws *Port already in use error* during upgrade.

#### Solution

If static port is used in existing deployment, before upgrade, in custom values file port needs to be updated to use another port to avoid port conflict error.

## 4.25 CNC Console Helm Test Fails

### CNC Console Helm Test Fails

**Problem:** CNC Console helm test fails when there are stale jobs or pods.

#### Solution

In some cases, Helm RC builds have intermittent issues which blocks auto deletion of jobs.

Ensure stable helm version is installed in your environment.

## 4.26 CNC Console Helm Test Fails with Service Account Error

### CNC Console Helm Test Fails with Service Account Error

**Problem:** CNC Console helm test fails when there are stale jobs or pods.

CNCC helm test fails with error message "Unauthorized! Configured service account doesn't have access. Service account may have been revoked."

#### Solution

The time sync between worker nodes is must for helm test to work. Ensure CNE worker nodes time is in sync.

## 4.27 Unable to integrate LDAP with Console deployed on ASM setup

### Unable to integrate LDAP with Console deployed on ASM setup

**Problem:** While integrating LDAP/LDAPs with CNC console, **Test Connection** is successful but **Test Authentication** fails. Generic error is displayed on screen "Error when trying to connect to LDAP. See server.log for details. LDAP test error "

#### Solution:

Apply the following yaml. This YAML sets up Kubernetes resources and Istio configurations to facilitate communication with an external LDAP connectivity service from within the cncc namespace. It ensures that internal services can access the external LDAP service using DNS resolution and defines routing and traffic policies specific to Istio.

```
kubectl apply -n cncc -f - <<EOF
apiVersion: v1
kind: Endpoints
metadata:
 name: <Unique ServiceEntry Name for Service>
 namespace: <CNCC-NAMESPACE>
subsets:
- addresses:
 - ip: <Service-public-IP>
 ports:
 - port: <Service-public-PORT>
 protocol: <Service-PROTOCOL>

apiVersion: v1
kind: Service
metadata:
 name: <Unique Endpoint Name for Service>-headless
 namespace: <CNCC-NAMESPACE>
spec:
 clusterIP: None
 ports:
 - port: <Service-public-PORT>
 protocol: <Service-PROTOCOL>
 targetPort: <Service-public-PORT>
 sessionAffinity: None
```

```

 type: ClusterIP

apiVersion: v1
kind: Service
metadata:
 name: <Unique ServiceEntry Name for Service>
 namespace: <CNCC-NAMESPACE>
spec:
 externalName: <Unique ServiceEntry Name for Service>-headless.<CNCC-
 NAMESPACE>.svc.cluster.local
 sessionAffinity: None
 type: ExternalName

apiVersion: networking.istio.io/v1alpha3
kind: ServiceEntry
metadata:
 name: <Unique ServiceEntry Name for Service>
 namespace: <CNCC-NAMESPACE>
spec:
 hosts:
 - <Service-public-FQDN>
 ports:
 - number: <Service-public-PORT>
 name: <Service-PORTNAME>
 location: MESH_EXTERNAL

apiVersion: networking.istio.io/v1alpha3
kind: DestinationRule
metadata:
 name: <Unique DestinationRule Name for Service>
 namespace: cncc
spec:
 host: <Service-public-FQDN>
 trafficPolicy:
 tls:
 mode: DISABLE

EOF

```

Example:

```

kubectl apply -n cncc -f - <<EOF
apiVersion: v1
kind: Endpoints
metadata:
 name: ldap-connectivity-service-headless
 namespace: cncc
subsets:
- addresses:
 - ip: 10.75.212.154
 ports:
 - port: 30763
 protocol: TCP

apiVersion: v1

```

```
kind: Service
metadata:
 name: ldap-connectivity-service-headless
 namespace: cncc
spec:
 clusterIP: None
 ports:
 - port: 30763
 protocol: TCP
 targetPort: 30763
 sessionAffinity: None
 type: ClusterIP

apiVersion: v1
kind: Service
metadata:
 name: ldap-connectivity-service
 namespace: cncc
spec:
 externalName: ldap-connectivity-service-headless.cncc.svc.cluster.local
 sessionAffinity: None
 type: ExternalName

apiVersion: networking.istio.io/v1alpha3
kind: ServiceEntry
metadata:
 name: ldap-external-se
 namespace: cncc
spec:
 hosts:
 - ldap-connectivity-service-headless.cncc.svc.cluster.local
 ports:
 - number: 30763
 name: ldap
 location: MESH_EXTERNAL

apiVersion: networking.istio.io/v1alpha3
kind: DestinationRule
metadata:
 name: ldap-external-dr
 namespace: cncc
spec:
 host: ldap-connectivity-service-headless.cncc.svc.cluster.local
 trafficPolicy:
 tls:
 mode: DISABLE

EOF
```

Once the yaml file is applied, LDAP Server can be integrated.

While setting up User Federation with CNCC IAM, when providing your company LDAP server details, connection URL needs to be configured using ldap-connectivity-service.

## 4.28 CNC Console IAM GUI gives an error while accessing some resources under master realm

CNC Console IAM GUI gives an error while accessing some resources under master realm.

### Problem:


CNC Console IAM GUI throws the following error when some resources are accessed under the master realm:

"Error: Could not find the resource that you are looking for. Press here to refresh and continue."

### Solution:

Some resources (APIs) are blocked under the "master realm" or "cncc realm" because of security reasons. This restricts the user from making any configuration changes. These resources are not applicable for Console. So, whenever the user tries to access blocked resources(APIs), the admin user always gets the error message asking the user to refresh and continue. It is expected behavior. Also note that CNC Console IAM is enabled with a single admin user. All admin operations must be carried out by the same admin user.

**Figure 4-1 Unable to Find Resource Error**



## 4.29 Unable to login to CNC Console Core when TLS version is v1.2 and Ciphers Other Than That of TLSv1.2 are Provided

**Problem:** CNC Console user is unable to log into CNC Console GUI.

After the user enters the username and password, the 503-service unavailable error is displayed on GUI. In Pod logs "The specified CipherSuites array contains invalid null or empty string elements" exception is seen.

The following conditions should occur for the issue to be observed:

1. IAM service is HTTPS.
2. M-CNCC Core or A-CNCC service has the TLS version set to TLSv1.2.
3. M-CNCC Core or A-CNCC service has ciphers other than that of TLSv1.2.

**Solution:** The user should specify the cipher suites applicable to the corresponding TLS version. Cipher Suites can be specified in custom values using `mcncc-core.ingress-gateway.cipherSuites` or `acncc-core.ingress-gateway.cipherSuites`.

For more information, see *Oracle communications, Cloud Native Configuration Console Installation, Upgrade, and Fault Recovery Guide*.

## 4.30 Database Connectivity Failure When Instance Level Access Control is Enabled

**Problem:** The operator faces database connectivity failure with the CNC Console IAM hook when the instance level access control feature is enabled.

**Solution:** When the connectivity is established again, operator must delete the `INSTANCE_ALL` role manually from the UI and run the installation for the CNC Console IAM hooks again to assign the `INSTANCE_ALL` role to the existing users.

## 4.31 403 Forbidden Error when Accessing NF or CS Resources With Instance Level Access Control Enabled

**Problem:** A user with some required permissions encounters the 403 forbidden error when they try to access any NF or CS resources.

**Solution:** Check the `acore-ingress-gateway` pod logs to identify the missing permissions for the user.

# 5

## CNC Console Troubleshooting in OCI Deployment

This section provides information to troubleshoot the common errors which can be encountered when CNC Console is deployed in OCI.

### 5.1 CNC Console Deployment pods are not coming up

#### CNC Console Deployment pods are not coming up

This error can arise due to the following problems -

**Problem 1:** *CreateContainerConfigError* is observed in *acore-ingress-gateway* and *mcore-ingress-gateway* pods.

**Solution:** Cross check if **oci-iam-secret** is created or not. If not, create the secret properly as mentioned in *Cloud Native Configuration Console Installation, Upgrade, and Fault Recovery Guide*.

**Problem 2:** *mcore-ingress-gateway* pods is going to *CrashLoopBackOff* state.

**Solution:** Please check the `ocncc_custom_values.yaml` file for the following -

1. Incorrect domain URL is provided in **global.mCncclams.fqdn** section of Instance configuration. This field should contain the URL of OCI Domain used to deploy CNC Console.

```
mCncclams:
 - id: Cluster1
 fqdn: idcs-37e739602b574bb6848c8cd96640f11d.identity.oraclecloud.com
 scheme: https
```

2. Scheme is missing in Instance Configuration of **global.mCncclams.scheme** User should provide **HTTPS** scheme.

**Problem 3:** *ImagePullBackOff* Error coming up for CNC Console Deployment pods.

**Solution:** All the image repositories must be public. Run the following steps to make all image repositories public:

1. Go to **OCI Console** → **Developer Services** → **Containers & Artifacts** → **Container Registry**.
2. Select the compartment.
3. In the **Repositories** and **Images Search** option, the images will be listed. Select each image and change to **Public**. This step must be performed for all the images sequentially.

**Problem 4:** A *CreateContainerConfigError* is seen in *cncc-mcore-validationhook*.

**Solution:** Verify that the `oci-iam-admin-secret` has been created. If not, create the secret by following the procedure described in the *Oracle Communications Cloud Native Configuration Console Installation, Upgrade, and Fault Recovery Guide*.

## 5.2 CNC Console Core GUI is not loading

### CNC Console Core GUI is not loading

**Problem:** Unable to access CNC Console Core GUI, getting "Invalid credentials" Error

This error can arise due to the following incorrect configurations -

- Incorrect Configuration 1: When **oci-iam-secret** is incorrect.  
**Solution:** Please make sure to create the secret properly as described in the *Oracle Communications Cloud Native Configuration Console Installation, Upgrade, and Fault Recovery Guide*.
- Incorrect Configuration 2: Incorrect **Issuer URL** is provided in OAuth settings of OCI IAM domain  
**Solution:** Follow the below steps to correct the Issuer URL in OAuth settings:
  1. Open the navigation menu and click **Identity & Security**. Under **Identity**, click **Domains**. Select the identity domain where CNC Console is deployed.
  2. Navigate to Security → OAuth
  3. Update the issuer URL with correct value (If the OCI IAM domain URL is with default port 80/443, make sure to remove the port from the domain URL while updating the **Issuer** field and it should match with what is provided in the **global.mCncclams.fqdn** section of `ocncc_custom_values.yaml`).

## 5.3 Getting invalid redirect uri error while accessing CNC Console Core

### Getting 'invalid redirect uri error' while accessing CNC Console Core

**Problem:** Getting the below error while accessing to CNC Console Core

```
{"error":"invalid_redirect_uri","error_description":"Client
c2151db267684a8fa15bcd19d56cd2a3 requested an invalid redirect URL: https://
100.xx.xx.xx/login/oauth2/code/cncc-iam. ECID:
0ZjBv13L9000000000"}
```

### Solution:

This problem is observed when incorrect redirect-uri is configured in the OAuth configuration of Integrated Application . Please follow the below steps -

1. Open the navigation menu and click **Identity & Security**. Under **Identity**, click **Domains**. Select the identity domain where CNC Console is deployed.
2. Click on **Integrated Applications**
3. Click on the Integrated Application that you want to modify. (Ex: **cncc-iam**)
4. Click **Edit OAuth Configuration**
5. Scroll down to find Redirect URL
6. Make sure to update the correct Redirect URL as per *Oracle Communications Cloud Native Configuration Console Installation, Upgrade, and Fault Recovery Guide*.

## 5.4 LDAP Integration Issues

### LDAP Integration Issues

**Problem 1:** Not Able to find Delegate Authentication option.

**Solution:** Check for Type of Domain, it should be Premium for Delegate Authentication.

**Problem 2:** Not Able to find The Active Directory's (AD) Organization Unit (OU) for user and group in Oracle Cloud Infrastructure IAM (OCI IAM) Console.

**Solution:**

1. Check for the Organizational Unit in Active Directory.
2. If Organizational Unit is present in Active Directory.
3. Refresh the web Browser.

**Problem 3:** Not Able to Authenticate User using Active Directory user's password

**Solution:**

1. Make sure **Enable local authentication** is Enabled in **Authentication Settings** of OCI IAM.
2. Provide the required permission to Active Directory administrator. For more information see, the *Oracle Cloud Infrastructure Documentation*.

## 5.5 Issues in SAML Authentication

### Issues in SAML Authentication

**Problem:** Logging in using SAML SSO throws following error: *No user was returned during the SAML assertion to user mapping for partner SSO*

**Solution:** In this case, recheck the SAML JIT configuration done in the **IDP** section of OCI IAM.

1. In the **Map User Attributes** section, check if the proper mapping is done between the IDP and Identity domain attributes.
2. If any of the IDP attribute mapped under this section is missing in SAML Assertion coming from IDP, then the authentication will fail.

## 5.6 CNC Console Access when private LoadBalancer IP is assigned

### CNC Console Access when private LoadBalancer IP is assigned

**Problem:** CNC Console GUIs cannot be accessed when private LoadBalancer IP is assigned using the annotation [oci-network-load-balancer.oraclecloud.com/internal](https://oci-network-load-balancer.oraclecloud.com/internal): "true"

**Solution:** Access the CNC Console GUI via tunneling.

You can use any online emulator available for tunneling or you can follow the below steps mentioned

1. Run the following command for tunnelling using ssh command

```
ssh -v -f -N -i <id_rsa_private_key> -o StrictHostKeyChecking=no -o ProxyCommand="ssh -i <id_rsa_private_key> -o StrictHostKeyChecking=no -W %h:%p <user>@<bastion_ip>" <user>@<operator_instance_ip> -L <local_port>:<worker_node_ip>:<loadbalancer_service_port> -o ServerAliveInterval=60 -o ServerAliveCountMax=300
```

Example:

```
ssh -v -f -N -i id_rsa -o StrictHostKeyChecking=no -o ProxyCommand="ssh -i id_rsa -o StrictHostKeyChecking=no -W %h:%p opc@10.xx.xx.xx" opc@10.xx.xx.xx -L 443:10.xx.xx.xx:31152 -o ServerAliveInterval=60 -o ServerAliveCountMax=300
```

where each attributes are

| Attribute                   | Description                                                                                                |
|-----------------------------|------------------------------------------------------------------------------------------------------------|
| <id_rsa_private_key>        | Specifies the private key to connect to the Bastion host.                                                  |
| <user>                      | username to connect to Bastion and Operator instances                                                      |
| <bastion_ip>                | IP of the bastion host                                                                                     |
| <operator_instance_ip>      | IP of the Operator instance                                                                                |
| <worker_node_ip>            | IP of the Worker node where CNC Console Application is installed                                           |
| <local_port>                | The port on your local machine where the browser is installed that requires forwarding from a remote host. |
| <loadbalancer_service_port> | Load Balancer service port of CNC Console, that is, M-CNCC Core ingress-gateway service                    |

2. Open the /etc/hosts file.

#### For Mac

- a. Open the Terminal application on your Mac computer.
- b. Access the /etc/ hosts folder using a text editor (sudo user).

#### For Windows

- a. Press the Windows key.
- b. Type Notepad in the search field.
- c. In the search results, right-click Notepad and select Run as administrator.
- d. From Notepad, open the following file: c:\Windows\System32\Drivers\etc\hosts

3. Add following entries under /etc/hosts file

For M-CNCC Core

```
127.0.0.1 <cncc_release_name>-mcore-ingress-gateway.<cncc_namespace>.svc.<cluster_domain>
```

Example:

```
127.0.0.1 cncc-mcore-ingress-gateway.cncc.svc.cluster.local
```

4. Access the CNC Console GUI using the above configured FQDN.

## 5.7 OCI IAM Connectivity Failure when Instance Level Access Control is Enabled

**Problem:** The operator faces database connectivity failure with the validation hook when the instance level access control feature is enabled.

**Solution:** When the connectivity is established again, operator must delete the INSTANCE\_ALL role manually from the UI and run the installation for the validation hooks again to assign the INSTANCE\_ALL role to the existing users.

## 5.8 403 Forbidden Error when Accessing NF Resources With Instance Level Access Control Enabled

**Problem:** A user with some required permissions encounters the 403 forbidden error when they try to access any NF resources.

**Solution:** Check the acore-ingress-gateway pod logs to identify the missing permissions for the user.

# 6

## CNC Console Alerts

This section provides information about CNC Console Alerts.

### Note

#### **For OCI:**

The only section applicable for OCI is [CNC Console Alerts on OCI](#).

### Note

Alert file is present in the Scripts directory. `occncc_csar_<version>.zip` can be downloaded from MOS. Unzip the file to get `occncc_alertrules_<version>.yaml` file.

- Review the `occncc_alerting_rules_promha_<version>.yaml` file and edit the value of the parameters in the `occncc_alerting_rules_promha_<version>.yaml` file (if needed to be changed from default values) before configuring the alerts.
- `kubernetes_namespace` is configured as `kubernetes` namespace in which CNCC is deployed. Default value is `cncc`. Update the `occncc_alertrules_<version>.yaml` file to reflect the correct CNCC kubernetes namespace.

Two sample Alert files are provided, one for supporting CNE 1.8 or lower and second one supporting CNE Prometheus HA.

- CNC Console Alert Rules file: `occncc_alertrules_<version>.yaml` file.
- CNC Console Alert Rules file supporting CNE Prometheus HA: `occncc_alerting_rules_promha_<version>.yaml` file.

## 6.1 CNC Console IAM Alerts

This section provides information about CNC Console IAM Alerts.

### 6.1.1 CncclamTotalIngressTrafficRateAboveMinorThreshold

**Table 6-1 CncclamTotalIngressTrafficRateAboveMinorThreshold**

|                   |                                                                                                                                                                                                                                                                                          |
|-------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Trigger Condition | The total CNCC IAM Ingress Message rate has crossed the configured minor threshold of 700 TPS.<br><br>Default value of this alert trigger point in <code>occncc_alertrules_&lt;version&gt;.yaml</code> is when CNCC IAM Ingress Rate crosses 70 % of 1000 (Maximum ingress request rate) |
| Severity          | Minor                                                                                                                                                                                                                                                                                    |

**Table 6-1 (Cont.) CnccIamTotalIngressTrafficRateAboveMinorThreshold**

|                         |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                   |
|-------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Alert details provided  | <p><b>Description:</b> CNCC IAM Ingress traffic Rate is above the configured minor threshold i.e. 700 requests per second (current value is: {{ \$value }})</p> <p><b>For CNE 1.9.0 or later versions:</b></p> <p><b>summary:</b> 'namespace: {{\$labels.namespace}}, podname: {{\$labels.pod}}, timestamp: {{ with query "time()" }}{{ .   first   value   humanizeTimestamp }}{{ end }}: Traffic Rate is above 70 Percent of Max requests per second(1000)'</p> <p><b>For CNE 1.8.x or previous versions:</b></p> <p><b>summary:</b> 'namespace: {{\$labels.kubernetes_namespace}}, podname: {{\$labels.kubernetes_pod_name}}, timestamp: {{ with query "time()" }}{{ .   first   value   humanizeTimestamp }}{{ end }}: Traffic Rate is above 70 Percent of Max requests per second(1000)'</p> |
| OID used for SNMP Traps | 1.3.6.1.4.1.323.5.3.51.1.2.7001                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                   |
| Metric Used             | oc_ingressgateway_http_requests_total                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |
| Resolution              | <p>The alert is cleared either when the total Ingress Traffic rate falls below the Minor threshold or when the total traffic rate crosses the Major threshold, in which case the <i>CnccIamTotalIngressTrafficRateAboveMajorThreshold</i> alert is raised.</p> <p><b>Note:</b> The threshold is configurable in the <i>occncc_alertrules_&lt;version&gt;.yaml</i> file.</p> <p>Steps:</p> <ol style="list-style-type: none"> <li>1. Reassess why the CNCC IAM is receiving additional traffic.</li> <li>2. If this is unexpected, contact My Oracle Support.</li> </ol>                                                                                                                                                                                                                           |

## 6.1.2 CnccIamTotalIngressTrafficRateAboveMajorThreshold

**Table 6-2 CnccIamTotalIngressTrafficRateAboveMajorThreshold**

|                         |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
|-------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Trigger Condition       | <p>The total CNCC IAM Ingress Message rate has crossed the configured major threshold of 800 TPS.</p> <p>Default value of this alert trigger point in <i>occncc_alertrules_&lt;version&gt;.yaml</i> is when CNCC IAM Ingress Rate crosses 80 % of 1000 (Maximum ingress request rate)</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                           |
| Severity                | Major                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               |
| Alert details provided  | <p><b>Description:</b> 'CNCC IAM Ingress traffic Rate is above the configured major threshold i.e. 800 requests per second (current value is: {{ \$value }})'</p> <p><b>For CNE 1.9.0 or later versions:</b></p> <p><b>summary:</b> 'namespace: {{\$labels.namespace}}, podname: {{\$labels.pod}}, timestamp: {{ with query "time()" }}{{ .   first   value   humanizeTimestamp }}{{ end }}: Traffic Rate is above 80 Percent of Max requests per second(1000)'</p> <p><b>For CNE 1.8.x or previous versions:</b></p> <p><b>summary:</b> 'namespace: {{\$labels.kubernetes_namespace}}, podname: {{\$labels.kubernetes_pod_name}}, timestamp: {{ with query "time()" }}{{ .   first   value   humanizeTimestamp }}{{ end }}: Traffic Rate is above 80 Percent of Max requests per second(1000)'</p> |
| OID used for SNMP Traps | 1.3.6.1.4.1.323.5.3.51.1.2.7001                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |

**Table 6-2 (Cont.) CncclamTotalIngressTrafficRateAboveMajorThreshold**

|             |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        |
|-------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Metric Used | oc_ingressgateway_http_requests_total                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  |
| Resolution  | <p>The alert is cleared when the total Ingress Traffic rate falls below the Major threshold or when the total traffic rate crosses the Critical threshold, in which case the <i>CncclamTotalIngressTrafficRateAboveCriticalThreshold</i> alert is raised.</p> <p><b>Note:</b> The threshold is configurable in the <i>occncc_alertrules_&lt;version&gt;.yaml</i> file.</p> <p>Steps:</p> <ol style="list-style-type: none"> <li>1. Reassess why the CNCC IAM is receiving additional traffic.</li> <li>2. If this is unexpected, contact My Oracle Support.</li> </ol> |

### 6.1.3 CncclamTotalIngressTrafficRateAboveCriticalThreshold

**Table 6-3 CncclamTotalIngressTrafficRateAboveCriticalThreshold**

|                         |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |
|-------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Trigger Condition       | The total CNCC IAM Ingress Message rate has crossed the configured critical threshold of 900TPS. Default value of this alert trigger point in <i>occncc_alertrules_&lt;version&gt;.yaml</i> is when CNCC IAM Ingress Rate crosses 90 % of 1000 (Maximum ingress request rate)                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                         |
| Severity                | Critical                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              |
| Alert details provided  | <p><b>Description:</b> CNCC IAM Ingress traffic Rate is above the configured critical threshold, that is, 900 requests per second (current value is: {{ \$value }})</p> <p><b>For CNE 1.9.0 or later versions:</b></p> <p><b>summary:</b> 'namespace: {{\$labels.namespace}}, podname: {{\$labels.pod}}, timestamp: {{ with query "time()" }}{ .   first   value   humanizeTimestamp }}{ end }}: Traffic Rate is above 90 Percent of Max requests per second(1000)'</p> <p><b>For CNE 1.8.x or previous versions:</b></p> <p><b>summary:</b> 'namespace: {{\$labels.kubernetes_namespace}}, podname: {{\$labels.kubernetes_pod_name}}, timestamp: {{ with query "time()" }}{ .   first   value   humanizeTimestamp }}{ end }}: Traffic Rate is above 90 Percent of Max requests per second(1000)'</p> |
| OID used for SNMP Traps | 1.3.6.1.4.1.323.5.3.51.1.2.7001                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |
| Metric Used             | oc_ingressgateway_http_requests_total                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
| Resolution              | <p>The alert is cleared when the Ingress Traffic rate falls below the Critical threshold.</p> <p><b>Note:</b> The threshold is configurable in the <i>occncc_alertrules_&lt;version&gt;.yaml</i> file.</p> <p>Steps:</p> <ol style="list-style-type: none"> <li>1. Reassess why the CNCC IAM is receiving additional traffic.</li> <li>2. If this is unexpected, contact My Oracle Support.</li> </ol>                                                                                                                                                                                                                                                                                                                                                                                                |

## 6.1.4 CncclamMemoryUsageCrossedMinorThreshold

**Table 6-4 CncclamMemoryUsageCrossedMinorThreshold**

|                         |                                                                                                                                                                                                                                                                                                                                                                                                       |
|-------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Trigger Condition       | A pod has reached the configured minor threshold( 70%) of its memory resource limits.                                                                                                                                                                                                                                                                                                                 |
| Severity                | Minor                                                                                                                                                                                                                                                                                                                                                                                                 |
| Alert details provided  | <p><b>Description:</b> 'CNCC IAM Memory Usage for pod {{ \$labels.pod }} has crossed the configured minor threshold (70%) (value={{ \$value }}) of its limit.'</p> <p><b>Summary:</b> 'namespace: {{ \$labels.namespace}}, podname: {{ \$labels.pod}}, timestamp: {{ with query "time()" }}{{ .   first   value   humanizeTimestamp }}{{ end }} : Memory Usage of pod exceeded 70% of its limit.'</p> |
| OID used for SNMP Traps | 1.3.6.1.4.1.323.5.3.51.1.2.7002                                                                                                                                                                                                                                                                                                                                                                       |
| Metric Used             | <p>container_memory_usage_bytes,<br/>kube_pod_container_resource_limits</p> <p><b>Note:</b>This is a Kubernetes metric used for instance availability monitoring. If the metric is not available, use a similar metric as exposed by the monitoring system.</p>                                                                                                                                       |
| Resolution              | <p>The alert gets cleared when the memory utilization falls below the Minor Threshold or crosses the major threshold, in which case <i>CncclamMemoryUsageCrossedMajorThreshold</i> alert is raised.</p> <p><b>Note:</b> The threshold is configurable in the <i>occncc_alertrules_&lt;version&gt;.yaml</i> file.</p> <p>If guidance is required, contact My Oracle Support.</p>                       |

## 6.1.5 CncclamMemoryUsageCrossedMajorThreshold

**Table 6-5 CncclamMemoryUsageCrossedMajorThreshold**

|                         |                                                                                                                                                                                                                                                                                                                                                                                                         |
|-------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Trigger Condition       | A pod has reached the configured major threshold( 80%) of its memory resource limits.                                                                                                                                                                                                                                                                                                                   |
| Severity                | Major                                                                                                                                                                                                                                                                                                                                                                                                   |
| Alert details provided  | <p><b>Description:</b> 'CNCC IAM Memory Usage for pod {{ \$labels.pod }} has crossed the configured major threshold (80%) (value = {{ \$value }}) of its limit.'</p> <p><b>Summary:</b> 'namespace: {{ \$labels.namespace}}, podname: {{ \$labels.pod}}, timestamp: {{ with query "time()" }}{{ .   first   value   humanizeTimestamp }}{{ end }} : Memory Usage of pod exceeded 80% of its limit.'</p> |
| OID used for SNMP Traps | 1.3.6.1.4.1.323.5.3.51.1.2.7002                                                                                                                                                                                                                                                                                                                                                                         |
| Metric Used             | <p>container_memory_usage_bytes,<br/>kube_pod_container_resource_limits</p> <p><b>Note:</b> This is a Kubernetes metric used for instance availability monitoring.If the metric is not available, use a similar metric as exposed by the monitoring system.</p>                                                                                                                                         |

**Table 6-5 (Cont.) CncclamMemoryUsageCrossedMajorThreshold**

|            |                                                                                                                                                                                                                                                                                                                                                                                          |
|------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Resolution | <p>The alert gets cleared when the memory utilization falls below the Major Threshold or crosses the critical threshold, in which case <i>CncclamMemoryUsageCrossedCriticalThreshold</i> alert shall be raised.</p> <p><b>Note:</b> The threshold is configurable in the <i>occncc_alertrules_&lt;version&gt;.yaml</i> file.<br/>If guidance is required, contact My Oracle Support.</p> |
|------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|

## 6.1.6 CncclamMemoryUsageCrossedCriticalThreshold

**Table 6-6 CncclamMemoryUsageCrossedCriticalThreshold**

|                         |                                                                                                                                                                                                                                                                                                                                                                                                             |
|-------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Trigger Condition       | A pod has reached the configured critical threshold ( 90% ) of its memory resource limits                                                                                                                                                                                                                                                                                                                   |
| Severity                | Critical                                                                                                                                                                                                                                                                                                                                                                                                    |
| Alert details provided  | <p><b>Description:</b> 'CNCC IAM Memory Usage for pod {{ \$labels.pod }} has crossed the configured critical threshold (90%) (value = {{ \$value }}) of its limit.'</p> <p><b>Summary:</b> 'namespace: {{ \$labels.namespace }}, podname: {{ \$labels.pod }}, timestamp: {{ with query "time()" }}{ .   first   value   humanizeTimestamp }}{{ end }} : Memory Usage of pod exceeded 90% of its limit.'</p> |
| OID used for SNMP Traps | 1.3.6.1.4.1.323.5.3.51.1.2.7002                                                                                                                                                                                                                                                                                                                                                                             |
| Metric Used             | <p>container_memory_usage_bytes,<br/>kube_pod_container_resource_limits</p> <p><b>Note:</b> This is a Kubernetes metric used for instance availability monitoring. If the metric is not available, use a similar metric as exposed by the monitoring system.</p>                                                                                                                                            |
| Resolution              | <p>The alert gets cleared when the memory utilization falls below the Critical Threshold.</p> <p>Note : The threshold is configurable in the <i>occncc_alertrules_&lt;version&gt;.yaml</i> file.<br/>If guidance is required, contact My Oracle Support.</p>                                                                                                                                                |

## 6.1.7 CncclamTransactionErrorRateAbove0.1Percent

**Table 6-7 CncclamTransactionErrorRateAbove0.1Percent**

|                         |                                                                                                                                                                                                                                                    |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Trigger Condition       | The number of failed transactions is above 0.1 percent of the total transactions.                                                                                                                                                                  |
| Severity                | Warning                                                                                                                                                                                                                                            |
| Alert details provided  | <p><b>Description:</b> 'CNCC IAM transaction Error rate is above 0.1 Percent of Total Transactions (current value is {{ \$value }})'</p> <p><b>Summary:</b> 'CNCC IAM transaction Error Rate detected above 0.1 Percent of Total Transactions'</p> |
| OID used for SNMP Traps | 1.3.6.1.4.1.323.5.3.51.1.2.7003                                                                                                                                                                                                                    |
| Metric Used             | oc_ingressgateway_http_responses_total                                                                                                                                                                                                             |

**Table 6-7 (Cont.) CncclamTransactionErrorRateAbove0.1Percent**

|            |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
|------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Resolution | <p>The alert is cleared when the number of failed transactions is below 0.1% of the total transactions or when the number of failed transactions crosses the 1% threshold in which case the <i>CncclamTransactionErrorRateAbove1Percent</i> is raised.</p> <p>Steps:</p> <ol style="list-style-type: none"> <li>1. Check the Service specific metrics to understand the specific service request errors.</li> <li>2. If guidance is required, contact My Oracle Support.</li> </ol> |
|------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|

## 6.1.8 CncclamTransactionErrorRateAbove1Percent

**Table 6-8 CncclamTransactionErrorRateAbove1Percent**

|                         |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
|-------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Trigger Condition       | The number of failed transactions is above 1 percent of the total transactions.                                                                                                                                                                                                                                                                                                                                                                                                     |
| Severity                | Warning                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |
| Alert details provided  | <p><b>Description:</b> 'CNCC IAM transaction Error rate is above 1 Percent of Total Transactions (current value is {{ \$value }})'</p> <p><b>Summary:</b> 'CNCC IAM transaction Error Rate detected above 1 Percent of Total Transactions'</p>                                                                                                                                                                                                                                      |
| OID used for SNMP Traps | 1.3.6.1.4.1.323.5.3.51.1.2.7003                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
| Metric Used             | oc_ingressgateway_http_responses_total                                                                                                                                                                                                                                                                                                                                                                                                                                              |
| Resolution              | <p>The alert is cleared when the number of failed transactions is below 1% of the total transactions or when the number of failed transactions crosses the 10% threshold in which case the <i>CncclamTransactionErrorRateAbove10Percent</i> is raised.</p> <p>Steps:</p> <ol style="list-style-type: none"> <li>1. Check the Service specific metrics to understand the specific service request errors.</li> <li>2. If guidance is required, contact My Oracle Support.</li> </ol> |

## 6.1.9 CncclamTransactionErrorRateAbove10Percent

**Table 6-9 CncclamTransactionErrorRateAbove10Percent**

|                         |                                                                                                                                                                                                                                                                            |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Trigger Condition       | The number of failed transactions is above 10 percent of the total transactions.                                                                                                                                                                                           |
| Severity                | Minor                                                                                                                                                                                                                                                                      |
| Alert details provided  | <p><b>Description:</b> CNCC IAM transaction Error rate is above 10 Percent of Total Transactions (current value is {{ \$value }})'</p> <p><b>Summary:</b> 'CNCC IAM transaction Error rate is above 10 Percent of Total Transactions (current value is {{ \$value }})'</p> |
| OID used for SNMP Traps | 1.3.6.1.4.1.323.5.3.51.1.2.7003                                                                                                                                                                                                                                            |
| Metric Used             | oc_ingressgateway_http_responses_total                                                                                                                                                                                                                                     |

**Table 6-9 (Cont.) CncclamTransactionErrorRateAbove10Percent**

|            |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      |
|------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Resolution | <p>The alert is cleared when the number of failed transactions is below 10% of the total transactions or when the number of failed transactions crosses the 25% threshold in which case the <i>CncclamTransactionErrorRateAbove25Percent</i> is raised.</p> <p>Steps:</p> <ol style="list-style-type: none"> <li>1. Check the Service specific metrics to understand the specific service request errors.</li> <li>2. If guidance is required, contact My Oracle Support.</li> </ol> |
|------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|

## 6.1.10 CncclamTransactionErrorRateAbove25Percent

**Table 6-10 CncclamTransactionErrorRateAbove25Percent**

|                         |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
|-------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Trigger Condition       | The number of failed transactions is above 25 percent of the total transactions.                                                                                                                                                                                                                                                                                                                                                                                                    |
| Severity                | Major                                                                                                                                                                                                                                                                                                                                                                                                                                                                               |
| Alert details provided  | <p><b>Description:</b> 'CNCC IAM transaction Error Rate detected above 25 Percent of Total Transactions (current value is {{ \$value }})'</p> <p><b>Summary:</b> 'CNCC IAM transaction Error Rate detected above 25 Percent of Total Transactions'</p>                                                                                                                                                                                                                              |
| OID used for SNMP Traps | 1.3.6.1.4.1.323.5.3.51.1.2.7003                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
| Metric Used             | oc_ingressgateway_http_responses_total                                                                                                                                                                                                                                                                                                                                                                                                                                              |
| Resolution              | <p>The alert is cleared when the number of failed transactions are below 25% of the total transactions or when the number of failed transactions cross the 50% threshold in which case the <i>CncclamTransactionErrorRateAbove50Percent</i> is raised.</p> <p>Steps:</p> <ol style="list-style-type: none"> <li>1. Check the Service specific metrics to understand the specific service request errors.</li> <li>2. If guidance is required, contact My Oracle Support.</li> </ol> |

## 6.1.11 CncclamTransactionErrorRateAbove50Percent

**Table 6-11 CncclamTransactionErrorRateAbove50Percent**

|                         |                                                                                                                                                                                                                       |
|-------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Trigger Condition       | The number of failed transactions is above 50 percent of the total transactions.                                                                                                                                      |
| Severity                | Critical                                                                                                                                                                                                              |
| Alert details provided  | <p><b>Description:</b> The number of failed transactions is above 50 percent of the total transactions.</p> <p><b>Summary:</b> 'CNCC IAM transaction Error Rate detected above 50 Percent of Total Transactions'.</p> |
| OID used for SNMP Traps | 1.3.6.1.4.1.323.5.3.51.1.2.7003                                                                                                                                                                                       |
| Metric Used             | oc_ingressgateway_http_responses_total                                                                                                                                                                                |

**Table 6-11 (Cont.) CnccIamTransactionErrorRateAbove50Percent**

|            |                                                                                                                                                                                                                                                                                                                                                                                                                                            |
|------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Resolution | <p>The alert is cleared when the number of failed transactions is below 50 percent of the total transactions.</p> <p>The threshold is configurable in the <i>occncc_alertrules_&lt;version&gt;.yaml</i> file.</p> <p>Steps:</p> <ol style="list-style-type: none"> <li>1. Check the Service specific metrics to understand the specific service request errors.</li> <li>2. If guidance is required, contact My Oracle Support.</li> </ol> |
|------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|

## 6.1.12 CnccIamIngressGatewayServiceDown

**Table 6-12 CnccIamIngressGatewayServiceDown**

|                         |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
|-------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Trigger Condition       | The pods of the CNCC IAM Ingress Gateway microservice is available.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |
| Severity                | Critical                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        |
| Alert details provided  | <p><b>Description:</b> 'CNCC IAM Ingress-Gateway service InstanceIdentifier=~".*cncc-iam_ingressgateway" is down'</p> <p><b>For CNE 1.9.0 or later versions:</b></p> <p><b>summary:</b> 'namespace: {{\$labels.namespace}}, podname: {{\$labels.pod}}, timestamp: {{ with query "time()" }}{{ .   first   value   humanizeTimestamp }}{{ end }} : Ingress-gateway service down'</p> <p><b>For CNE 1.8.x or previous versions:</b></p> <p><b>summary:</b> 'namespace: {{\$labels.kubernetes_namespace}}, podname: {{\$labels.kubernetes_pod_name}}, timestamp: {{ with query "time()" }}{{ .   first   value   humanizeTimestamp }}{{ end }} : Ingress-gateway service down'</p> |
| OID used for SNMP Traps | 1.3.6.1.4.1.323.5.3.51.1.2.7004                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
| Metric Used             | <p>'up'</p> <p><b>Note:</b> This is a Prometheus metric used for instance availability monitoring. If this metric is not available, use a similar metric as exposed by the monitoring system.</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                               |
| Resolution              | <p>The alert is cleared when the cncc-iam_ingressgateway service is available.</p> <p>Steps:</p> <ol style="list-style-type: none"> <li>1. Check the orchestration logs of cncc-iam_ingressgateway service and check for liveness or readiness probe failures.</li> <li>2. Refer to the application logs on Kibana and filter based on cncc-iam_ingressgateway service names. Check for ERROR WARNING logs related to thread exceptions.</li> <li>3. Depending on the failure reason, take the resolution steps.</li> <li>4. In case the issue persists, contact My Oracle Support.</li> </ol>                                                                                  |

## 6.1.13 CncclamFailedLogin

**Table 6-13 CncclamFailedLogin**

|                         |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Trigger Condition       | The count of failed login attempts in CNCC-IAM by a user goes above '3'                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            |
| Severity                | Warning                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            |
| Alert details provided  | <p><b>Description:</b> '{{ \$value }}' failed Login attempts have been detected in CNCC IAM for user {{ \$labels.UserName }}, the configured threshold value is 3 failed login attempts for every 5 min'</p> <p><b>For CNE 1.9.0 or later versions:</b><br/> <b>summary:</b> 'namespace: {{ \$labels.namespace }}, podname: {{ \$labels.pod }}, timestamp: {{ with query "time()" }}{ .   first   value   humanizeTimestamp }}{{ end }}: failed login attempts are more than the configured threshold value'</p> <p><b>For CNE 1.8.x or previous versions:</b><br/> <b>summary:</b> 'namespace: {{ \$labels.kubernetes_namespace }}, podname: {{ \$labels.kubernetes_pod_name }}, timestamp: {{ with query "time()" }}{ .   first   value   humanizeTimestamp }}{{ end }}: failed login attempts are more than the configured threshold value'</p> |
| OID used for SNMP Traps | 1.3.6.1.4.1.323.5.3.51.1.2.7005                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    |
| Metric Used             | oc_ingressgateway_http_responses_total                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |
| Resolution              | <p>The alert gets cleared when the total failed login attempts for a particular user goes below the threshold value (default value is '3') in the last 5 min (default value is 5 m).</p> <p><b>Note:</b> The threshold and time is configurable in the <i>alerts.yaml</i> file.<br/>If guidance is required, contact My Oracle Support.</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        |

## 6.1.14 AdminUserCreation

**Table 6-14 AdminUserCreation**

|                         |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |
|-------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Trigger Condition       | If a new admin account is created in the last 5 min                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                         |
| Severity                | Warning                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
| Alert details provided  | <p><b>For CNE 1.9.0 or later versions:</b><br/> <b>Description:</b> '{{ \$value }}' admin users have been created by {{ \$labels.UserName }} '<br/> <b>summary:</b> 'namespace: {{ \$labels.namespace }}'<br/> <b>summary:</b> {{ \$labels.pod }}, user: {{ \$labels.UserName }}, timestamp: {{ with query "time()" }}{ .   first   value   humanizeTimestamp }}{{ end }}: Admin users have been created '</p> <p><b>For CNE 1.8.x or previous versions:</b><br/> <b>Description:</b> '{{ \$value }}' admin users have been created by {{ \$labels.UserName }} '<br/> <b>summary:</b> 'namespace: {{ \$labels.kubernetes_namespace }}'<br/> <b>summary:</b> {{ \$labels.kubernetes_pod_name }}, user: {{ \$labels.UserName }}, timestamp: {{ with query "time()" }}{ .   first   value   humanizeTimestamp }}{{ end }}: Admin users have been created '</p> |
| OID used for SNMP Traps | 1.3.6.1.4.1.323.5.3.51.1.2.7006                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |
| Metric Used             | oc_ingressgateway_http_requests_total                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |

**Table 6-14 (Cont.) AdminUserCreation**

|            |                                                                                                                                                                                                                                                                                                                                                                                                                               |
|------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Resolution | <p>The alert gets cleared when the total failed login attempts for a particular user go below the threshold value (default value is '3') in the last 5 min (default value is 5 m)</p> <p><b>Note:</b> The threshold and time is configurable in the <i>occncc_alertrules_&lt;version&gt;.yaml</i> file.</p> <p>Login to admin GUI and review the user created.</p> <p>If guidance is required, contact My Oracle Support.</p> |
|------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|

## 6.1.15 CncclamAccessTokenFailure

**Table 6-15 CncclamAccessTokenFailure**

|                         |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      |
|-------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Trigger Condition       | If the count of failed token for CNCC-IAM goes above configured value of '3'                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                         |
| Severity                | Warning                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              |
| Alert details provided  | <p><b>Description:</b> 'CNCC iam Access Token Failure count is above the configured value i.e. 3 for every 5 min. Failed access token request count per second is (current value is: {{ \$value }})'</p> <p><b>For CNE 1.9.0 or later versions:</b></p> <p><b>summary:</b> 'namespace: {{ \$labels.namespace }}, podname: {{ \$labels.pod }}, timestamp: {{ with query "time()" }}{{ .   first   value   humanizeTimestamp }}{{ end }}: Access Token Failure count is above the configured threshold value'</p> <p><b>For CNE 1.8.x or previous versions:</b></p> <p><b>summary:</b> 'namespace: {{ \$labels.kubernetes_namespace }}, podname: {{ \$labels.pod }}, timestamp: {{ with query "time()" }}{{ .   first   value   humanizeTimestamp }}{{ end }}: Access Token Failure count is above the configured threshold value'</p> |
| OID used for SNMP Traps | 1.3.6.1.4.1.323.5.3.51.1.2.7007                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      |
| Metric Used             | oc_ingressgateway_http_responses_total                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               |
| Resolution              | <p>The alert gets cleared when the total failed tokens for a particular user go below the threshold value (default value is '3') in the last 5 min (default value is 5 m)</p> <p><b>Note:</b> The threshold and time is configurable in the <i>occncc_alertrules_&lt;version&gt;.yaml</i> file.</p> <p>If guidance is required, contact My Oracle Support.</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |

## 6.2 CNC Console Core Alerts

This section provides the information about CNC Console Core Alerts.

## 6.2.1 CnccCoreTotalIngressTrafficRateAboveMinorThreshold

**Table 6-16 CnccCoreTotalIngressTrafficRateAboveMinorThreshold**

|                         |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |
|-------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Trigger Condition       | The total CNCC Core Ingress Message rate has crossed the configured minor threshold of 700 TPS.<br><br>Default value of this alert trigger point in <code>cncc_alert_rules.yaml</code> is when CNCC Core Ingress Rate crosses 70 % of 1000 (Maximum ingress request rate)                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |
| Severity                | Minor                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
| Alert details provided  | <b>Description:</b> 'CNCC Core Ingress traffic Rate is above the configured minor threshold i.e. 700 requests per second (current value is: {{ \$value }})'<br><br><b>For CNE 1.9.0 or later versions:</b><br><b>summary:</b> 'namespace: {{\$labels.namespace}}, podname: {{\$labels.kubernetes_pod_name}}, timestamp: {{ with query "time()" }}{{ .   first   value   humanizeTimestamp }}{{ end }}: Traffic Rate is above 70 Percent of Max requests per second(1000)'<br><br><b>For CNE 1.8.x or previous versions:</b><br><b>summary:</b> 'namespace: {{\$labels.kubernetes_namespace}}, podname: {{\$labels.kubernetes_pod_name}}, timestamp: {{ with query "time()" }}{{ .   first   value   humanizeTimestamp }}{{ end }}: Traffic Rate is above 70 Percent of Max requests per second(1000)' |
| OID used for SNMP Traps | 1.3.6.1.4.1.323.5.3.51.1.2.8001                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |
| Metric Used             | oc_ingressgateway_http_requests_total                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
| Resolution              | The alert is cleared either when the total Ingress traffic rate falls below the minor threshold or when the total traffic rate crosses the major threshold, in which case the <i>CnccCoreTotalIngressTrafficRateAboveMajorThreshold</i> alert is raised.<br><br><b>Note:</b> The threshold is configurable in the <code>occncc_alertrules_&lt;version&gt;.yaml</code> file.<br><br>Steps:<br><br><ol style="list-style-type: none"><li>1. Reassess why the CNCC Core is receiving additional traffic.</li><li>2. If this is unexpected, contact My Oracle Support.</li></ol>                                                                                                                                                                                                                          |

## 6.2.2 CnccCoreTotalIngressTrafficRateAboveMajorThreshold

**Table 6-17 CnccCoreTotalIngressTrafficRateAboveMajorThreshold**

|                   |                                                                                                                                                                                                                                                                           |
|-------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Trigger Condition | The total CNCC Core Ingress Message rate has crossed the configured major threshold of 800 TPS.<br><br>Default value of this alert trigger point in <code>cncc_alert_rules.yaml</code> is when CNCC Core Ingress Rate crosses 80 % of 1000 (Maximum ingress request rate) |
| Severity          | Major                                                                                                                                                                                                                                                                     |

**Table 6-17 (Cont.) CnccCoreTotalIngressTrafficRateAboveMajorThreshold**

|                         |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  |
|-------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Alert details provided  | <p><b>Description:</b> 'CNCC Core Ingress traffic Rate is above the configured major threshold i.e. 800 requests per second (current value is: {{ \$value }})'</p> <p><b>For CNE 1.9.0 or later versions:</b><br/> <b>summary:</b> 'namespace: {{\$labels.namespace}}, podname: {{\$labels.pod}}, timestamp: {{ with query "time()" }}{{ .   first   value   humanizeTimestamp }}{{ end }}: Traffic Rate is above 80 Percent of Max requests per second(1000)'</p> <p><b>For CNE 1.8.x or previous versions:</b><br/> <b>summary:</b> 'namespace: {{\$labels.kubernetes_namespace}}, podname: {{\$labels.kubernetes_pod_name}}, timestamp: {{ with query "time()" }}{{ .   first   value   humanizeTimestamp }}{{ end }}: Traffic Rate is above 80 Percent of Max requests per second(1000)'</p> |
| OID used for SNMP Traps | 1.3.6.1.4.1.323.5.3.51.1.2.8001                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  |
| Metric Used             | oc_ingressgateway_http_requests_total                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            |
| Resolution              | <p>The alert is cleared when the total Ingress Traffic rate falls below the Major threshold or when the total traffic rate crosses the Critical threshold, in which case the CnccCoreTotalIngressTrafficRate Above CriticalThreshold.</p> <p><b>Note:</b> The threshold is configurable in the <i>alerts.yaml</i> file.</p> <p>Steps:</p> <ol style="list-style-type: none"> <li>1. Reassess why the CNCC Core is receiving additional traffic.</li> <li>2. If this is unexpected, contact My Oracle Support.</li> </ol>                                                                                                                                                                                                                                                                         |

## 6.2.3 CnccCoreTotalIngressTrafficRateAboveCriticalThreshold

**Table 6-18 CnccCoreTotalIngressTrafficRateAboveCriticalThreshold**

|                         |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
|-------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Trigger Condition       | <p>The total CNCC Core Ingress Message rate has crossed the configured critical threshold of 900TPS.</p> <p>Default value of this alert trigger point in <i>cncc_alert_rules.yaml</i> is when CNCC Core Ingress Rate crosses 90 % of 1000 (Maximum ingress request rate)</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        |
| Severity                | Critical                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            |
| Alert details provided  | <p><b>Description:</b> 'CNCC Core Ingress traffic Rate is above the configured critical threshold i.e. 900 requests per second (current value is: {{ \$value }})'</p> <p><b>For CNE 1.9.0 or later versions:</b><br/> <b>summary:</b> 'namespace: {{\$labels.namespace}}, podname: {{\$labels.pod}}, timestamp: {{ with query "time()" }}{{ .   first   value   humanizeTimestamp }}{{ end }}: Traffic Rate is above 90 Percent of Max requests per second(1000)'</p> <p><b>For CNE 1.8.x or previous versions:</b><br/> <b>summary:</b> 'namespace: {{\$labels.kubernetes_namespace}}, podname: {{\$labels.kubernetes_pod_name}}, timestamp: {{ with query "time()" }}{{ .   first   value   humanizeTimestamp }}{{ end }}: Traffic Rate is above 90 Percent of Max requests per second(1000)'</p> |
| OID used for SNMP Traps | 1.3.6.1.4.1.323.5.3.51.1.2.8001                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
| Metric Used             | oc_ingressgateway_http_requests_total                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               |

**Table 6-18 (Cont.) CnccCoreTotalIngressTrafficRateAboveCriticalThreshold**

|            |                                                                                                                                                                                                                                                                                                                                                                                                        |
|------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Resolution | <p>The alert is cleared when the Ingress Traffic rate falls below the Critical threshold.</p> <p><b>Note:</b> The threshold is configurable in the <i>occncc_alertrules_&lt;version&gt;.yaml</i> file.</p> <p>Steps:</p> <ol style="list-style-type: none"> <li>1. Reassess why the CNCC IAM is receiving additional traffic.</li> <li>2. If this is unexpected, contact My Oracle Support.</li> </ol> |
|------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|

## 6.2.4 CnccCoreMemoryUsageCrossedMinorThreshold

**Table 6-19 CnccCoreMemoryUsageCrossedMinorThreshold**

|                         |                                                                                                                                                                                                                                                                                                                                                                                                        |
|-------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Trigger Condition       | A pod has reached the configured minor threshold( 70%) of its memory resource limits.                                                                                                                                                                                                                                                                                                                  |
| Severity                | Minor                                                                                                                                                                                                                                                                                                                                                                                                  |
| Alert details provided  | <p><b>Description:</b> 'CNCC Core Memory Usage for pod {{ \$labels.pod }} has crossed the configured minor threshold (70%) (value={{ \$value }}) of its limit.'</p> <p><b>Summary:</b> 'namespace: {{ \$labels.namespace }}, podname: {{ \$labels.pod }}, timestamp: {{ with query "time()" }}{ .   first   value   humanizeTimestamp }}{ end }} : Memory Usage of pod exceeded 70% of its limit.'</p> |
| OID used for SNMP Traps | 1.3.6.1.4.1.323.5.3.51.1.2.8002                                                                                                                                                                                                                                                                                                                                                                        |
| Metric Used             | <p>container_memory_usage_bytes</p> <p>kube_pod_container_resource_limits</p> <p>Note : This is a kubernetes metric used for instance availability monitoring. If the metric is not available, use the similar metric as exposed by the monitoring system.</p>                                                                                                                                         |
| Resolution              | <p>The alert gets cleared when the memory utilization falls below the Minor Threshold or crosses the major threshold, in which case CnccCoreMemoryUsageCrossedMajorThreshold alert is raised.</p> <p><b>Note:</b> The threshold is configurable in the <i>occncc_alertrules_&lt;version&gt;.yaml</i> file.</p> <p>If guidance is required, contact My Oracle Support.</p>                              |

## 6.2.5 CnccCoreMemoryUsageCrossedMajorThreshold

**Table 6-20 CnccCoreMemoryUsageCrossedMajorThreshold**

|                   |                                                                                       |
|-------------------|---------------------------------------------------------------------------------------|
| Trigger Condition | A pod has reached the configured major threshold( 80%) of its memory resource limits. |
| Severity          | Major                                                                                 |

**Table 6-20 (Cont.) CnccCoreMemoryUsageCrossedMajorThreshold**

|                         |                                                                                                                                                                                                                                                                                                                                                                                                 |
|-------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Alert details provided  | <b>Description:</b> 'CNCC Core Memory Usage for pod {{ \$labels.pod }} has crossed the configured major threshold (80%) (value = {{ \$value }}) of its limit.'<br><b>Summary:</b> 'namespace: {{ \$labels.namespace }}, podname: {{ \$labels.pod }}, timestamp: {{ with query "time()" }}{{ .   first   value   humanizeTimestamp }}{{ end }} : Memory Usage of pod exceeded 80% of its limit.' |
| OID used for SNMP Traps | 1.3.6.1.4.1.323.5.3.51.1.2.8002                                                                                                                                                                                                                                                                                                                                                                 |
| Metric Used             | container_memory_usage_bytes<br>kube_pod_container_resource_limits<br>Note : This is a kubernetes metric used for instance availability monitoring. If the metric is not available, use the similar metric as exposed by the monitoring system.                                                                                                                                                 |
| Resolution              | The alert gets cleared when the memory utilization falls below the Major Threshold or crosses the critical threshold, in which case CnccCoreMemoryUsageCrossedCriticalThreshold alert is raised<br><b>Note:</b> The threshold is configurable in the <i>occncc_alertrules_&lt;version&gt;.yaml</i> file.<br>If guidance is required, contact My Oracle Support.                                 |

## 6.2.6 CnccCoreMemoryUsageCrossedCriticalThreshold

**Table 6-21 CnccCoreMemoryUsageCrossedCriticalThreshold**

|                         |                                                                                                                                                                                                                                                                                                                                                                                                    |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Trigger Condition       | A pod has reached the configured critical threshold ( 90% ) of its memory resource limits                                                                                                                                                                                                                                                                                                          |
| Severity                | Critical                                                                                                                                                                                                                                                                                                                                                                                           |
| Alert details provided  | <b>Description:</b> 'CNCC Core Memory Usage for pod {{ \$labels.pod }} has crossed the configured critical threshold (90%) (value = {{ \$value }}) of its limit.'<br><b>Summary:</b> 'namespace: {{ \$labels.namespace }}, podname: {{ \$labels.pod }}, timestamp: {{ with query "time()" }}{{ .   first   value   humanizeTimestamp }}{{ end }} : Memory Usage of pod exceeded 90% of its limit.' |
| OID used for SNMP Traps | 1.3.6.1.4.1.323.5.3.51.1.2.8002                                                                                                                                                                                                                                                                                                                                                                    |
| Metric Used             | container_memory_usage_bytes<br>kube_pod_container_resource_limits<br>Note : This is a Kubernetes metric used for instance availability monitoring. If the metric is not available, use the similar metric as exposed by the monitoring system.                                                                                                                                                    |
| Resolution              | The alert gets cleared when the memory utilization falls below the Critical Threshold.<br><b>Note:</b> The threshold is configurable in the <i>occncc_alertrules_&lt;version&gt;.yaml</i> file.<br>If guidance is required, contact My Oracle Support.                                                                                                                                             |

## 6.2.7 CnccCoreTransactionErrorRateAbove0.1Percent

**Table 6-22 CnccCoreTransactionErrorRateAbove0.1Percent**

|                         |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                          |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Trigger Condition       | The number of failed transactions is above 0.1 percent of the total transactions..                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |
| Severity                | Warning                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  |
| Alert details provided  | <b>Description:</b> 'CNCC Core transaction Error rate is above 0.1 Percent of Total Transactions (current value is {{ \$value }})'<br><b>Summary:</b> 'CNCC Core transaction Error rate is above 0.1 Percent of Total Transactions (current value is {{ \$value }})'                                                                                                                                                                                                                                                                                     |
| OID used for SNMP Traps | 1.3.6.1.4.1.323.5.3.51.1.2.8003                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                          |
| Metric Used             | oc_ingressgateway_http_responses_total                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                   |
| Resolution              | <p>The alert is cleared when the number of failed transactions are below 0.1% of the total transactions or when the number of failed transactions cross the 1% threshold in which case the <i>CnccCoreTransactionErrorRateAbove1Percent</i> is raised.</p> <p>The threshold is configurable in the <i>alerts.yaml</i> file.</p> <p>Steps:</p> <ol style="list-style-type: none"> <li>1. Check the Service specific metrics to understand the specific service request errors.</li> <li>2. If guidance is required, contact My Oracle Support.</li> </ol> |

## 6.2.8 CnccCoreTransactionErrorRateAbove1Percent

**Table 6-23 CnccCoreTransactionErrorRateAbove1Percent**

|                         |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      |
|-------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Trigger Condition       | The number of failed transactions is above 1 percent of the total transactions.                                                                                                                                                                                                                                                                                                                                                                                                      |
| Severity                | Warning                                                                                                                                                                                                                                                                                                                                                                                                                                                                              |
| Alert details provided  | <b>Description:</b> 'CNCC Core transaction Error rate is above 1 Percent of Total Transactions (current value is {{ \$value }})'<br><b>Summary:</b> 'CNCC Core transaction Error Rate detected above 1 Percent of Total Transactions'                                                                                                                                                                                                                                                |
| OID used for SNMP Traps | 1.3.6.1.4.1.323.5.3.51.1.2.8003                                                                                                                                                                                                                                                                                                                                                                                                                                                      |
| Metric Used             | oc_ingressgateway_http_responses_total                                                                                                                                                                                                                                                                                                                                                                                                                                               |
| Resolution              | <p>The alert is cleared when the number of failed transactions are below 1% of the total transactions or when the number of failed transactions crosses the 10% threshold in which case the <i>CnccCoreTransactionErrorRateAbove10Percent</i> is raised.</p> <p>Steps:</p> <ol style="list-style-type: none"> <li>1. Check the Service specific metrics to understand the specific service request errors.</li> <li>2. If guidance is required,contact My Oracle Support.</li> </ol> |

## 6.2.9 CnccCoreTransactionErrorRateAbove10Percent

**Table 6-24 CnccCoreTransactionErrorRateAbove10Percent**

|                         |                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |
|-------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Trigger Condition       | The number of failed transactions is above 10 percent of the total transactions.                                                                                                                                                                                                                                                                                                                                                                                            |
| Severity                | Minor                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |
| Alert details provided  | <b>Description:</b> 'CNCC Core transaction Error rate is above 10 Percent of Total Transactions (current value is {{ \$value }})'<br><b>summary:</b> 'CNCC Core transaction Error Rate detected above 10 Percent of Total Transactions'                                                                                                                                                                                                                                     |
| OID used for SNMP Traps | 1.3.6.1.4.1.323.5.3.51.1.2.8003                                                                                                                                                                                                                                                                                                                                                                                                                                             |
| Metric Used             | oc_ingressgateway_http_responses_total                                                                                                                                                                                                                                                                                                                                                                                                                                      |
| Resolution              | The alert is cleared when the number of failed transactions are below 10% of the total transactions or when the number of failed transactions crosses the 25% threshold in which case the <i>CnccCoreTransactionErrorRateAbove25Percent</i> is raised.<br>Steps:<br><ol style="list-style-type: none"><li>1. Check the Service specific metrics to understand the specific service request errors.</li><li>2. If guidance is required, contact My Oracle Support.</li></ol> |

## 6.2.10 CnccCoreTransactionErrorRateAbove25Percent

**Table 6-25 CnccCoreTransactionErrorRateAbove25Percent**

|                         |                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |
|-------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Trigger Condition       | The number of failed transactions is above 25 percent of the total transactions.                                                                                                                                                                                                                                                                                                                                                                                            |
| Severity                | Major                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |
| Alert details provided  | <b>Description:</b> 'CNCC Core transaction Error Rate detected above 25 Percent of Total Transactions (current value is {{ \$value }})'<br><b>Summary:</b> 'CNCC Core transaction Error Rate detected above 25 Percent of Total Transactions'                                                                                                                                                                                                                               |
| OID used for SNMP Traps | 1.3.6.1.4.1.323.5.3.51.1.2.8003                                                                                                                                                                                                                                                                                                                                                                                                                                             |
| Metric Used             | oc_ingressgateway_http_responses_total                                                                                                                                                                                                                                                                                                                                                                                                                                      |
| Resolution              | The alert is cleared when the number of failed transactions are below 25% of the total transactions or when the number of failed transactions crosses the 50% threshold in which case the <i>CnccCoreTransactionErrorRateAbove50Percent</i> is raised.<br>Steps:<br><ol style="list-style-type: none"><li>1. Check the Service specific metrics to understand the specific service request errors.</li><li>2. If guidance is required, contact My Oracle Support.</li></ol> |

## 6.2.11 CnccCoreTransactionErrorRateAbove50Percent

**Table 6-26 CnccCoreTransactionErrorRateAbove50Percent**

|                         |                                                                                                                                                                                                                                                                                                                                 |
|-------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Trigger Condition       | The number of failed transactions is above 50 percent of the total transactions.                                                                                                                                                                                                                                                |
| Severity                | Critical                                                                                                                                                                                                                                                                                                                        |
| Alert details provided  | <b>Description:</b> 'CNCC Core transaction Error Rate detected above 50 Percent of Total Transactions (current value is {{ \$value }})'<br><b>Summary:</b> 'CNCC Core transaction Error Rate detected above 50 Percent of Total Transactions'                                                                                   |
| OID used for SNMP Traps | 1.3.6.1.4.1.323.5.3.51.1.2.8003                                                                                                                                                                                                                                                                                                 |
| Metric Used             | oc_ingressgateway_http_responses_total                                                                                                                                                                                                                                                                                          |
| Resolution              | The alert is cleared when the number of failed transactions are below 50 percent of the total transactions<br>Steps: <ol style="list-style-type: none"> <li>1. Check the Service specific metrics to understand the specific service request errors.</li> <li>2. If guidance is required, contact My Oracle Support.</li> </ol> |

## 6.2.12 CnccCoreIngressGatewayServiceDown

**Table 6-27 CnccCoreIngressGatewayServiceDown**

|                         |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               |
|-------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Trigger Condition       | Cncc Core Ingress Gateway service is down                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
| Severity                | Critical                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      |
| Alert details provided  | <b>Description:</b> 'CNCC Core Ingress-Gateway service InstanceIdentifier=~".*core_ingressgateway" is down'<br><b>For CNE 1.9.0 or later versions:</b><br><b>summary:</b> 'namespace: {{ \$labels.namespace }}, podname: {{ \$labels.pod }}, timestamp: {{ with query "time()" }}{{ .   first   value   humanizeTimestamp }}{{ end }} : Ingress-gateway service down'<br><b>For CNE 1.8.x or previous versions:</b><br><b>summary:</b> 'namespace: {{ \$labels.kubernetes_namespace }}, podname: {{ \$labels.kubernetes_pod_name }}, timestamp: {{ with query "time()" }}{{ .   first   value   humanizeTimestamp }}{{ end }} : Ingress-gateway service down' |
| OID used for SNMP Traps | 1.3.6.1.4.1.323.5.3.51.1.2.8004                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               |
| Metric Used             | 'up'<br>Note: This is a Prometheus metric used for instance availability monitoring. If this metric is not available, use a similar metric as exposed by the monitoring system.                                                                                                                                                                                                                                                                                                                                                                                                                                                                               |

**Table 6-27 (Cont.) CnccCoreIngressGatewayServiceDown**

|            |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |
|------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Resolution | <p>The alert is cleared when the <code>cncc-core_ingressgateway</code> service is available.</p> <p>Steps:</p> <ol style="list-style-type: none"> <li>1. Check the orchestration logs of <code>cncc-core_ingressgateway</code> service and check for liveness or readiness probe failures.</li> <li>2. Refer the application logs on Kibana and filter based on <code>cncc-core_ingressgateway</code> service names. Check for ERROR WARNING logs related to thread exceptions.</li> <li>3. Depending on the failure reason, take the resolution steps.</li> <li>4. In case the issue persists, contact My Oracle Support.</li> </ol> |
|------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|

## 6.2.13 CnccCoreFailedLogin

**Table 6-28 CnccCoreFailedLogin**

|                         |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |
|-------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Trigger Condition       | The count of failed login attempts in CNCC-Core by a user goes above '3'                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              |
| Severity                | Warning                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               |
| Alert details provided  | <p><b>Description:</b> '{{ \$value }}' failed Login attempts have been detected in CNCC Core for user {{ \$labels.UserName }}, the configured threshold value is 3 failed login attempts for every 5 min'</p> <p><b>For CNE 1.9.0 or later versions:</b><br/> <b>summary:</b> 'namespace: {{ \$labels.namespace }}, podname: {{ \$labels.pod }}, timestamp: {{ with query "time()" }}{{ .   first   value   humanizeTimestamp }}{{ end }}: failed login attempts are more than the configured threshold value'</p> <p><b>For CNE 1.8.x or previous versions:</b><br/> <b>summary:</b> 'namespace: {{ \$labels.kubernetes_namespace }}, podname: {{ \$labels.kubernetes_pod_name }}, timestamp: {{ with query "time()" }}{{ .   first   value   humanizeTimestamp }}{{ end }}: failed login attempts are more than the configured threshold value'</p> |
| OID used for SNMP Traps | 1.3.6.1.4.1.323.5.3.51.1.2.8005                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |
| Metric Used             | oc_ingressgateway_http_responses_total                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                |
| Resolution              | <p>The alert gets cleared when the total failed login attempts for a particular user go below the threshold value (default value is '3') in the last 5 min (default value is 5 m)</p> <p><b>Note:</b> The threshold and time is configurable in the <code>alerts.yaml</code> file. If guidance is required, contact My Oracle Support.</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            |

## 6.2.14 CnccCoreUnauthorizedAccess

**Table 6-29 CnccCoreUnauthorizedAccess**

|                   |                                                                          |
|-------------------|--------------------------------------------------------------------------|
| Trigger Condition | The count of failed login attempts in CNCC-Core by a user goes above '3' |
| Severity          | Warning                                                                  |

Table 6-29 (Cont.) CnccCoreUnauthorizedAccess

|                         |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            |
|-------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Alert details provided  | <p><b>Description:</b> '{{ \$value }}' Unauthorized Accesses have been detected in CNCC-Core for {{ \$labels.ResourceType }} for {{ \$labels.Method }} request. The configured threshold value is 3 for every 5 min'</p> <p><b>For CNE 1.9.0 or later versions:</b><br/> <b>summary:</b> 'namespace: {{ \$labels.namespace }}, podname: {{ \$labels.pod }}, timestamp: {{ with query "time()" }}{{ .   first   value   humanizeTimestamp }}{{ end }}: Unauthorized Access for CNCC-Core are more than threshold value'</p> <p><b>For CNE 1.8.x or previous versions:</b><br/> <b>summary:</b> 'namespace: {{ \$labels.kubernetes_namespace }}, podname: {{ \$labels.kubernetes_pod_name }}, timestamp: {{ with query "time()" }}{{ .   first   value   humanizeTimestamp }}{{ end }}: Unauthorized Access for CNCC-Core are more than threshold value'</p> |
| OID used for SNMP Traps | 1.3.6.1.4.1.323.5.3.51.1.2.8006                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            |
| Metric Used             | oc_ingressgateway_http_responses_total                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
| Resolution              | <p>The alert gets cleared when the total failed login attempts for a particular user go below the threshold value (default value is '3') in the last 5 min (default value is 5 m)</p> <p><b>Note:</b> The threshold and time is configurable in the alerts.yaml<br/> If guidance is required, contact My Oracle Support.</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               |

## 6.2.15 CnccCoreAccessTokenFailure

Table 6-30 CnccCoreAccessTokenFailure

|                         |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                   |
|-------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Trigger Condition       | If the count of failed token for CNCC-Core goes above configured value of '3'                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
| Severity                | Warning                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                           |
| Alert details provided  | <p><b>Description:</b> 'CNCC Core Access Token Failure count is above the configured value i.e. 3 for every 5 min. Failed access token request count per second is (current value is: {{ \$value }})'</p> <p><b>For CNE 1.9.0 or later versions:</b><br/> <b>summary:</b> 'namespace: {{ \$labels.namespace }}, podname: {{ \$labels.kubernetes_pod_name }}, timestamp: {{ with query "time()" }}{{ .   first   value   humanizeTimestamp }}{{ end }}: Access Token Failure count is above the configured threshold value'</p> <p><b>For CNE 1.8.x or previous versions:</b><br/> <b>summary:</b> 'namespace: {{ \$labels.kubernetes_namespace }}, podname: {{ \$labels.kubernetes_pod_name }}, timestamp: {{ with query "time()" }}{{ .   first   value   humanizeTimestamp }}{{ end }}: Access Token Failure count is above the configured threshold value'</p> |
| OID used for SNMP Traps | 1.3.6.1.4.1.323.5.3.51.1.2.8007                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                   |
| Metric Used             | oc_ingressgateway_http_responses_total                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            |
| Resolution              | <p>The alert gets cleared when the total failed tokens for a particular user go below the threshold value (default value is '3') in the last 5 min (default value is 5 m)</p> <p><b>Note:</b> The threshold and time is configurable in the <i>alerts.yaml</i> file.<br/> If guidance is required, Contact My Oracle Support.</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |

## 6.3 CNC Console Alerts on OCI

This section provides information about CNC Console Alerts on OCI:

### 6.3.1 CnccCoreTotalIngressTrafficRateAboveMinorThreshold

**Table 6-31 CnccCoreTotalIngressTrafficRateAboveMinorThreshold**

|                        |                                                                                                                                                                                                                                                                                                                                                                                                                                                               |
|------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Trigger Condition      | The total CNCC Core Ingress Message rate has crossed the configured minor threshold of 700 TPS.<br>Default value of this alert trigger point in <code>cncc_alert_rules.yaml</code> is when CNCC Core Ingress Rate crosses 70 % of 1000 (Maximum ingress request rate)                                                                                                                                                                                         |
| Severity               | minor                                                                                                                                                                                                                                                                                                                                                                                                                                                         |
| Alert details provided | CNCC Core Ingress traffic Rate is above the configured minor threshold i.e. 700 requests per second                                                                                                                                                                                                                                                                                                                                                           |
| Metric Used            | <code>oc_ingressgateway_http_requests_total</code>                                                                                                                                                                                                                                                                                                                                                                                                            |
| Resolution             | The alert is cleared either when the total Ingress Traffic rate falls below the Minor threshold or when the total traffic rate cross the Major threshold, in which case the <code>CnccCoreTotalIngressTrafficRateAboveMajorThreshold</code> alert shall be raised. Note: The threshold is configurable in the <code>alerts.yaml</code> . Steps: Reassess why the CNCC Core is receiving additional traffic. If this is unexpected, contact My Oracle Support. |

### 6.3.2 CnccCoreTotalIngressTrafficRateAboveMajorThreshold

**Table 6-32 CnccCoreTotalIngressTrafficRateAboveMajorThreshold**

|                        |                                                                                                                                                                                                                                                                                                                                                                                        |
|------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Trigger Condition      | The total CNCC Core Ingress Message rate has crossed the configured major threshold of 800 TPS.<br>Default value of this alert trigger point in <code>cncc_alert_rules.yaml</code> is when CNCC Core Ingress Rate crosses 80 % of 1000 (Maximum ingress request rate)                                                                                                                  |
| Severity               | major                                                                                                                                                                                                                                                                                                                                                                                  |
| Alert details provided | CNCC Core Ingress traffic Rate is above the configured major threshold i.e. 800 requests per second                                                                                                                                                                                                                                                                                    |
| Metric Used            | <code>oc_ingressgateway_http_requests_total</code>                                                                                                                                                                                                                                                                                                                                     |
| Resolution             | The alert is cleared when the total Ingress Traffic rate falls below the Major threshold or when the total traffic rate cross the Critical threshold, in which case the <code>CnccCoreTotalIngressTrafficRateAboveCriticalThreshold</code> alert shall be raised. Steps: Reassess why the CNCC Core is receiving additional traffic. If this is unexpected, contact My Oracle Support. |

### 6.3.3 CnccCoreTotalIngressTrafficRateAboveCriticalThreshold

**Table 6-33 CnccCoreTotalIngressTrafficRateAboveCriticalThreshold**

|                        |                                                                                                                                                                                                                                                                    |
|------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Trigger Condition      | The total CNCC Core Ingress Message rate has crossed the configured critical threshold of 900TPS.<br>Default value of this alert trigger point in cncc_alert_rules.yaml is when CNCC Core Ingress Rate crosses 90 % of 1000 (Maximum ingress request rate)         |
| Severity               | critical                                                                                                                                                                                                                                                           |
| Alert details provided | CNCC Core Ingress traffic Rate is above the configured critical threshold i.e. 900 requests per second                                                                                                                                                             |
| Metric Used            | oc_ingressgateway_http_requests_total                                                                                                                                                                                                                              |
| Resolution             | The alert is cleared when the Ingress Traffic rate falls below the Critical threshold. Note: The threshold is configurable in the alerts.yaml Steps: Reassess why the CNCC Core is receiving additional traffic. If this is unexpected, contact My Oracle Support. |

### 6.3.4 CnccCoreMemoryUsageCrossedMinorThreshold

**Table 6-34 CnccCoreMemoryUsageCrossedMinorThreshold**

|                        |                                                                                                                                                                                                                                                                                                                |
|------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Trigger Condition      | A pod has reached the configured minor threshold( 70%) of its memory resource limits.                                                                                                                                                                                                                          |
| Severity               | minor                                                                                                                                                                                                                                                                                                          |
| Alert details provided | CNCC Core Memory Usage for pod has crossed the configured minor threshold (70%) of its limit.                                                                                                                                                                                                                  |
| Metric Used            | container_memory_usage_bytes<br>Note : This is a kubernetes metric used for instance availability monitoring. If the metric is not available, use the similar metric as exposed by the monitoring system.                                                                                                      |
| Resolution             | The alert gets cleared when the memory utilization falls below the Minor Threshold or crosses the major threshold, in which case CnccCoreMemoryUsageCrossedMajorThreshold alert shall be raised<br>Note : The threshold is configurable in the alerts.yaml<br>If guidance required, Contact My Oracle Support. |

### 6.3.5 CnccCoreMemoryUsageCrossedMajorThreshold

**Table 6-35 CnccCoreMemoryUsageCrossedMajorThreshold**

|                        |                                                                                               |
|------------------------|-----------------------------------------------------------------------------------------------|
| Trigger Condition      | A pod has reached the configured major threshold( 80%) of its memory resource limits.         |
| Severity               | major                                                                                         |
| Alert details provided | CNCC Core Memory Usage for pod has crossed the configured major threshold (80%) of its limit. |

**Table 6-35 (Cont.) CnccCoreMemoryUsageCrossedMajorThreshold**

|             |                                                                                                                                                                                                                                                                                                                      |
|-------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Metric Used | container_memory_usage_bytes<br>Note : This is a kubernetes metric used for instance availability monitoring. If the metric is not available, use the similar metric as exposed by the monitoring system.                                                                                                            |
| Resolution  | The alert gets cleared when the memory utilization falls below the Major Threshold or crosses the critical threshold, in which case CnccCoreMemoryUsageCrossedCriticalThreshold alert shall be raised<br>Note : The threshold is configurable in the alerts.yaml<br>If guidance required, Contact My Oracle Support. |

### 6.3.6 CnccCoreMemoryUsageCrossedCriticalThreshold

**Table 6-36 CnccCoreMemoryUsageCrossedCriticalThreshold**

|                        |                                                                                                                                                                                                           |
|------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Trigger Condition      | A pod has reached the configured critical threshold ( 90% ) of its memory resource limits                                                                                                                 |
| Severity               | critical                                                                                                                                                                                                  |
| Alert details provided | CNCC Core Memory Usage for pod has crossed the configured critical threshold (90%) of its limit.                                                                                                          |
| Metric Used            | container_memory_usage_bytes<br>Note : This is a kubernetes metric used for instance availability monitoring. If the metric is not available, use the similar metric as exposed by the monitoring system. |
| Resolution             | The alert gets cleared when the memory utilization falls below the Critical Threshold.<br>Note : The threshold is configurable in the alerts.yaml<br>If guidance required, Contact My Oracle Support.     |

### 6.3.7 CnccCoreTransactionErrorRateAbovePointOnePercent

**Table 6-37 CnccCoreTransactionErrorRateAbovePointOnePercent**

|                        |                                                                                                                                                                                                                                                                                                                                                                                                          |
|------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Trigger Condition      | The number of failed transactions is above 0.1 percent of the total transactions.                                                                                                                                                                                                                                                                                                                        |
| Severity               | warning                                                                                                                                                                                                                                                                                                                                                                                                  |
| Alert details provided | CNCC Core transaction Error rate is above 0.1 Percent of Total Transactions                                                                                                                                                                                                                                                                                                                              |
| Metric Used            | oc_ingressgateway_http_responses_total                                                                                                                                                                                                                                                                                                                                                                   |
| Resolution             | The alert is cleared when the number of failure transactions are below 0.1% of the total transactions or when the number of failure transactions cross the 1% threshold in which case the CnccCoreTransactionErrorRateAbove1Percent shall be raised. Steps: 1. Check the Service specific metrics to understand the specific service request errors. 2. If guidance required, contact My Oracle Support. |

## 6.3.8 CnccCoreTransactionErrorRateAboveOnePercent

**Table 6-38 CnccCoreTransactionErrorRateAboveOnePercent**

|                        |                                                                                                                                                                                                                                                                                                                                                                                                          |
|------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Trigger Condition      | The number of failed transactions is above 1 percent of the total transactions.                                                                                                                                                                                                                                                                                                                          |
| Severity               | warning                                                                                                                                                                                                                                                                                                                                                                                                  |
| Alert details provided | CNCC Core transaction Error rate is above 1 Percent of Total Transactions                                                                                                                                                                                                                                                                                                                                |
| Metric Used            | oc_ingressgateway_http_responses_total                                                                                                                                                                                                                                                                                                                                                                   |
| Resolution             | The alert is cleared when the number of failure transactions are below 1% of the total transactions or when the number of failure transactions cross the 10% threshold in which case the CnccCoreTransactionErrorRateAbove10Percent shall be raised. Steps: 1. Check the Service specific metrics to understand the specific service request errors. 2. If guidance required, contact My Oracle Support. |

## 6.3.9 CnccCoreTransactionErrorRateAboveTenPercent

**Table 6-39 CnccCoreTransactionErrorRateAboveTenPercent**

|                        |                                                                                                                                                                                                                                                                                                                                                                                                           |
|------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Trigger Condition      | The number of failed transactions is above 10 percent of the total transactions.                                                                                                                                                                                                                                                                                                                          |
| Severity               | minor                                                                                                                                                                                                                                                                                                                                                                                                     |
| Alert details provided | CNCC Core transaction Error rate is above 10 Percent of Total Transactions                                                                                                                                                                                                                                                                                                                                |
| Metric Used            | oc_ingressgateway_http_responses_total                                                                                                                                                                                                                                                                                                                                                                    |
| Resolution             | The alert is cleared when the number of failure transactions are below 10% of the total transactions or when the number of failure transactions cross the 25% threshold in which case the CnccCoreTransactionErrorRateAbove25Percent shall be raised. Steps: 1. Check the Service specific metrics to understand the specific service request errors. 2. If guidance required, contact My Oracle Support. |

## 6.3.10 CnccCoreTransactionErrorRateAboveTwentyFivePercent

**Table 6-40 CnccCoreTransactionErrorRateAboveTwentyFivePercent**

|                        |                                                                                                                                                                                                                                                                                                                                                                                                           |
|------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Trigger Condition      | The number of failed transactions is above 25 percent of the total transactions.                                                                                                                                                                                                                                                                                                                          |
| Severity               | major                                                                                                                                                                                                                                                                                                                                                                                                     |
| Alert details provided | CNCC Core transaction Error Rate detected above 25 Percent of Total Transactions                                                                                                                                                                                                                                                                                                                          |
| Metric Used            | oc_ingressgateway_http_responses_total                                                                                                                                                                                                                                                                                                                                                                    |
| Resolution             | The alert is cleared when the number of failure transactions are below 25% of the total transactions or when the number of failure transactions cross the 50% threshold in which case the CnccCoreTransactionErrorRateAbove50Percent shall be raised. Steps: 1. Check the Service specific metrics to understand the specific service request errors. 2. If guidance required, contact My Oracle Support. |

## 6.3.11 CnccCoreTransactionErrorRateAboveFiftyPercent

**Table 6-41 CnccCoreTransactionErrorRateAboveFiftyPercent**

|                        |                                                                                                                                                                                                                                                               |
|------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Trigger Condition      | The number of failed transactions is above 50 percent of the total transactions.                                                                                                                                                                              |
| Severity               | critical                                                                                                                                                                                                                                                      |
| Alert details provided | CNCC Core transaction Error Rate detected above 50 Percent of Total Transactions                                                                                                                                                                              |
| Metric Used            | oc_ingressgateway_http_responses_total                                                                                                                                                                                                                        |
| Resolution             | The alert is cleared when the number of failure transactions are below 50 percent of the total transactions.Steps:1. Check the Service specific metrics to understand the specific service request errors.2. If guidance required, contact My Oracle Support. |

## 6.3.12 CnccCoreUnauthorizedAccess

**Table 6-42 CnccCoreUnauthorizedAccess**

|                        |                                                                                                                                                                                                                                                                                                            |
|------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Trigger Condition      | If the count of unauthorized access goes above the configured value of '3'                                                                                                                                                                                                                                 |
| Severity               | warning                                                                                                                                                                                                                                                                                                    |
| Alert details provided | Unauthorized Accesses have been detected in CNCC-Core for request. The configured threshold value is 3 for every 5 min                                                                                                                                                                                     |
| Metric Used            | oc_ingressgateway_http_responses_total                                                                                                                                                                                                                                                                     |
| Resolution             | The alert gets cleared when the total unauthorized accesses for a particular user go below the threshold value (default value is '3') in the last 5 min (default value is 5 m)<br><br>Note : The threshold and time is configurable in the alerts.yaml<br>If guidance required, Contact My Oracle Support. |