# Oracle Utilities Extractors and Schema for Oracle Utilities Mobile Workforce Management

Data Mapping Guide Release 2.8.0.2.0 **F90736-01** 

December 2023



Oracle Utilities Extractors and Schema for Oracle Utilities Mobile Workforce Management Release 2.8.0.2.0 Data Mapping Guide

F90736-01

Copyright © 2000, 2023 Oracle and/or its affiliates.

# Contents

Preface	1
Audience	ii
Documentation Accessibility	ii
Related Documents	11
Conventions	
Acronyms	iii
Chapter 1	
Overview	1-1
Terminologies	1-1
<table name=""></table>	1-1
Chapter 2	
Data Maps for Oracle Utilities Mobile Workforce Management	2-1
Dimensions	
Appointment Time	2-2
Appointment Time of Day	2-5
Crew Shift	2-7
Crew Time Usage	2-10
Early Logoff Time	2-12
Late Logon Time	2-16
Response Time Deviation	2-19
Shift BO Status	2-22
Task BO Status	2-24
Task Type	2-27
Travel Distance Deviation	2-29
Travel Duration Deviation	2-32
Work Duration Deviation	2-35
Shared Dimensions	2-38
Account	2-38
Address	2-38
Crew	2-56
Contact	2-60
Device	2-60
Person	2-61
Premise	2-61
Service Agreement	2-61
Service Point	2-61
Usage Subscription	2-62
Facts	2-63
Completed Shift	2-63
Crew Task	2-71
Field Activity	2-78

# **Preface**

Welcome to Oracle Utilities Extractors and Schema for Oracle Utilities Mobile Workforce Management Data Mapping Guide.

This guide provides the data mapping information from the Oracle Utilities Extractors and Schema for Oracle Utilities Mobile Workforce Management source system to the Oracle Utilities Extractors and Schema target product.

- Audience
- Documentation Accessibility
- Related Documents
- Conventions
- Acronyms

#### **Audience**

The guide is intended for all implementers of Oracle Utilities Extractors and Schema for Oracle Utilities Extractors and Schema for Oracle Utilities Mobile Workforce Management.

### **Documentation Accessibility**

For information about configuring and using accessibility features for Oracle Utilities Analytics Warehouse, see the documentation at http://docs.oracle.com/cd/E23943\_01/bi.1111/e10544/appaccess.htm#BIEUG2756.

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at http://www.oracle.com/us/corporate/accessibility/index.html.

#### Access to Oracle Support

Oracle customers have access to electronic support through My Oracle Support. For more information, visit: http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info or http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs if you are hearing impaired.

#### **Related Documents**

Refer to the Oracle Utilities Analytics Warehouse Installation and Configuration Checklist for high-level steps to install and configure the Oracle Utilities Analytics Warehouse product. **Note** that this checklist includes information for Release 2.7.0.2.

The following documentation is included in this release.

#### Installation, Administration, and Release Notes

- Oracle Utilities Analytics Warehouse Release Notes
- Oracle Utilities Analytics Warehouse Getting Started Guide
- Oracle Utilities Analytics Warehouse Licensing Information User Manual
- Oracle Utilities Analytics Warehouse Installation and Configuration Guide
- Oracle Utilities Analytics Warehouse Quick Install Guide
- Oracle Utilities Analytics Warehouse Developer's Guide

#### Metric Reference Guides

Refer to the Oracle Utilities Analytics Warehouse documentation on Oracle Help Center for details about the metric reference guides included in this release.

#### **Data Mapping Guides**

Refer to the Oracle Utilities Analytics Warehouse documentation on Oracle Help Center for details about the data mapping guides included in this release.

#### See Also:

• Oracle Utilities Mobile Workforce Management Documentation Library

# **Conventions**

The following notational conventions are used in this document:

Notation	Indicates
boldface	Graphical user interface elements associated with an action, terms defined in text, or terms defines in the glossary
italic	Book titles, emphasis, or placeholder variables for which you supply particular values
monospace	Commands within a paragraph, URLs, code in examples, text that appears on the screen, or text that you enter

# **Acronyms**

The following terms are used in this document:

Term	Indicates
MWM	Oracle Utilities Mobile Workforce Management
ETL	Extraction, Transformation, and Loading
ODI	Oracle Data Integrator
OAS	Oracle Analytics Server
OUAF	Oracle Utilities Application Framework
OUAW	Oracle Utilities Analytics Warehouse

# Chapter 1 Overview

This guide provides the data mapping information from the Oracle Utilities Mobile Workforce Management source system to the Oracle Utilities Extractors and Schema target product, along with the rules of data transformation.

# **Terminologies**

This section describes the terminology used for data maps included in the document.

#### <Table Name>

The Table Name indicates the name of the fact or the dimension in a star schema in the data warehouse.

#### **Properties**

The Properties table lists properties of the table independent of each field. The following properties are listed in the table:

Property	Value
Target Table	Name of the table in the target schema (data warehouse) into which data is loaded
Table Type	Fact or Dimension
SCD Type	Type 1 - Existing records are updated directly. The nature of the dimension depends on how it handles changes made in the source system.
	Type 2 - When changes occur, a new effective row is inserted. The existing records are deactivated by entering the current date as the effective end date and new records are inserted with an effective start date as today's date. The new record will have the end date as a high date.

Property	Value	
Fact Type	Whether this is a snapshot or accumulation fact table	
	Snapshot - Captures a snapshot view of the data as available in the source system during that period (monthly or weekly). Each snapshot's data is stored independently.	
	Accumulation - Data from the source system is accumulated periodically. Changes from source system will be merged with the existing data. Multiple copies of the same data will not be maintained.	
Source System Driver Table	Name of the table in source database on which the data is primarily based	
Source System Download Table	Name of the download table populated by the source batch program.	
	Note that this property is applicable only for the snapshot facts for which special batch programs have been designed in the source system for data extraction.	
Stage Table	Name of the table in the staging schema (data warehouse) that can be used to query the data records generated by the ETL logic	
Oracle Data Integrator Package	Name of the ODI package that needs to be executed to transform data from the replication layer and populate a specific target table in the data warehouse	
ETL View	Resides in the replication layer and fetches the base values from the replication tables as a starting point for further transformations to be done by the Oracle Data Integrator interfaces	
Materialized View	Names of the materialized views delivered with the product for a specific fact table	
	These materialized views are designed to support all of the OAS answers delivered with the product. Refreshing these materialized views will be taken care by separate ETL jobs.	
Source Batch Program	The batch program that needs to be executed in the MDM system to extract the data into download tables. This is available only for the MDM snapshot facts.	

#### **Fields**

The Fields table lists the individual properties of each field in the Presentation table or the Database table. The following fields are listed in the tables:

Property	Value
Target Field	Name of the column in the fact or dimension table present in the data warehouse. The extracted/transformed data is loaded here.
Description	Description of the target field

Property	Value
Source Field	Name of the field from the source application used to load the target field either directly or after transformation
Transformation Logic	Specifies the details of how the data from the source field is transformed before being populated into the target field.

#### **Field Categories**

This table lists the categories under which the fields in a particular fact or dimension are grouped. The categories presented are as below:

Category	Details	
Surrogate Key	The primary key on the fact/dimension table maintained within the data warehouse.	
Natural Keys	The set of columns from the source system define the granularity of the fact or dimension table. The natural key columns from the source along with certain other data load attributes can be used to uniquely identify a record in the table.	
	The additional columns needed for the identification depend on the type of the table as listed below:	
	SCD Type 1 Dimension - Data Source Indicator	
	<ul> <li>SCD Type 2 Dimension - Effective Start Date, Effective End Date, Data Source Indicator</li> </ul>	
	Accumulation Fact - Data Source Indicator	
	Snapshot Fact - Snapshot Date, Data Source Indicator	
Attributes	Hold descriptive data from the source system and are typically available in dimension tables.	
Measures	Hold numerical value based data calculated from the source system data and are typically available on fact tables.	
Degenerate Dimensions	Hold descriptive data from the source system and are typically available in fact tables. These cannot be grouped into any of the available dimensions.	
Foreign Keys	Foreign key references on the fact tables to the dimension tables.	
User Defined Attributes	Additional fields available to customers for extending the star schemas. These fields will not be populated out of the box. Customers need to customize the ETL and populate these fields.	
Data Load Attributes	Hold the date/time information, job number details, etc, related to the ETL processes, that are needed for audit purposes.	

# Chapter 2

# Data Maps for Oracle Utilities Mobile Workforce Management

This chapter contains data maps for the following Oracle Utilities Extractors and Schema for Oracle Utilities Mobile Workforce Management tables:

- Dimensions
- Shared Dimensions
- Facts

# **Dimensions**

This section lists all the dimension tables belonging to the Oracle Utilities Mobile Workforce Management star schemas only and are populated only from the Oracle Utilities Mobile Workforce Management source product.

#### **Appointment Time**

Stores the time ranges in minutes indicating whether the crew missed an appointment, and if so, by how much time.

#### **Properties**

Property	Value
Target Table	CD_APPT_TM
Table Type	Dimension
SCD Type	Type 1
Source System Driver Table	F1_BKT_CONFIG
Stage Table	STG_CD_APPT_TM
ODI Package	B1_PKG_CD_APPT_TM
ETL View	B1_D_APPT_VW

Target Field	Description	Source Field	Transformation Logic
	Description	oource ricia	Transformation Logic
Surrogate Key			
APPT_TM_KEY	Appointment Time Dimension Surrogate Key		This field is populated from the OUBI_APPT_TM_SEQ sequence.
Natural Keys			
START_RANGE	Appointment Time Start Range	F1_BKT_CONFIG_VAL.B KT_START_RANGE	This field is populated with the bucket start range based on the bucket configuration code.
			The bucket configuration code from the Bucket Configuration table is retrieved based on the bucket configuration BO defined for appointment time.

Target Field	Description	Source Field	Transformation Logic
END_RANGE	Appointment Time End Range	F1_BKT_CONFIG_VAL.B KT_END_RANGE	The field is populated with the bucket end range based on the bucket configuration code.
			The bucket configuration code from the Bucket Configuration table is retrieved based on the bucket configuration BO defined for appointment time.
Attributes			
APPT_TM_DESCR	Appointment Time Description	F1_BKT_CONFIG_VAL_ L.DESCR	
APPT_STATUS_DESCR	Appointment Status Description	CI_LOOKUP_VAL_L.DE SCR_OVRD	This field is populated with the description from Lookup
		CI_LOOKUP_VAL_L.DE SCR	Language table for M1_APPT_STATUS_FLG lookup field.
			If override description is not available, regular description is extracted.
APPT_STATUS_CD	Appointment Status Code	F1_BKT_CONFIG_VAL.B KT_VAL_TYPE_CD	
APPT_TM_CD	Appointment Time Code		Note: This field is obsolete and is not populated. The new bucket configurations based on the OUAF bucket configuration tables do not need this.
User Defined Attributes			
UDF1_CD	User Defined Field 1 Code		
UDF1_DESCR	User Defined Field 1 Description		
UDF2_CD	User Defined Field 2 Code		
UDF2_DESCR	User Defined Field 2 Description		
UDF3_CD	User Defined Field 3 Code		
UDF3_DESCR	User Defined Field 3 Description		
UDF4_CD	User Defined Field 4 Code		
UDF4_DESCR	User Defined Field 4 Description		
UDF5_CD	User Defined Field 5 Code		

Target Field	Description	Source Field	Transformation Logic
UDF5_DESCR	User Defined Field 5 Description		
UDF6_CD	User Defined Field 6 Code		
UDF6_DESCR	User Defined Field 6 Description		
UDF7_CD	User Defined Field 7 Code		
UDF7_DESCR	User Defined Field 7 Description		
UDF8_CD	User Defined Field 8 Code		
UDF8_DESCR	User Defined Field 8 Description		
UDF9_CD	User Defined Field 9 Code		
UDF9_DESCR	User Defined Field 9 Description		
UDF10_CD	User Defined Field 10 Code		
UDF10_DESCR	User Defined Field 10 Description		
Data Load Attributes			
UPDATE_DTTM	Update Date and Time		
DATA_LOAD_DTTM	Data Load Date/Time		This field is populated with the load timestamp value.
DATA_SOURCE_IND	Data Source Indicator	CI_INSTALLATION.ENV _ID	This field is populated with the DSI value on the source product instance configuration. The table is populated as part of the initial setup and the DSI value is extracted from the environment ID of the source system.
JOB_NBR	Job Number		This field is populated with the ODI job execution session number.

**Note**: This bucket dimension is configured as one time load only. For information about data reload, see **Reloading the Bucket Configuration** section in the *Oracle Utilities Analytics Warehouse Installation and Configuration Guide*.

# **Appointment Time of Day**

Stores time ranges classifying an appointment time of day.

#### **Properties**

Property	Value
Target Table	CD_APPT_TM_OF_DAY
Table Type	Dimension
SCD Type	Type 1
Source System Driver Table	F1_BKT_CONFIG
Stage Table	STG_CD_APPT_TM_OF_DAY
ODI Package	B1_PKG_CD_APPT_TM_OF_DAY
ETL View	B1_D_APPT_OF_DAY_VW

Target Field	Description	Source Field	Transformation Logic
Surrogate Key			
APPT_TM_OF_DAY_KEY	Appointment Time of Day Dimension Surrogate Key		This field is populated from the OUBI_APPT_TM_OF_DAY _SEQ sequence.
Natural Keys			
START_RANGE	Appointment Time of Day Start Range	F1_BKT_CONFIG_VAL.B KT_START_RANGE	The field is populated with the bucket start range based on the bucket configuration code.
			The bucket configuration code from the Bucket Configuration table is retrieved based on the bucket configuration BO defined for appointment time of day.
END_RANGE	Appointment Time of Day End Range	F1_BKT_CONFIG_VAL.B KT_END_RANGE	The field is populated with the bucket end range based on the bucket configuration code.
			The bucket configuration code from the Bucket Configuration table is retrieved based on the bucket configuration BO defined for appointment time of day.

Target Field	Description	Source Field	Transformation Logic
Attributes			
APPT_TM_OF_DAY_DES CR	Appointment Time of Day Description	F1_BKT_CONFIG_VAL_ L.DESCR	
APPT_TM_OF_DAY_CD	Appointment Time Of Day Code		Note: This field is obsolete and is not populated. The new bucket configurations based on the OUAF bucket configuration tables do not need this.
User Defined Attributes			
UDF1_CD	User Defined Field 1 Code		
UDF1_DESCR	User Defined Field 1 Description		
UDF2_CD	User Defined Field 2 Code		
UDF2_DESCR	User Defined Field 2 Description		
UDF3_CD	User Defined Field 3 Code		
UDF3_DESCR	User Defined Field 3 Description		
UDF4_CD	User Defined Field 4 Code		
UDF4_DESCR	User Defined Field 4 Description		
UDF5_CD	User Defined Field 5 Code		
UDF5_DESCR	User Defined Field 5 Description		
UDF6_CD	User Defined Field 6 Code		
UDF6_DESCR	User Defined Field 6 Description		
UDF7_CD	User Defined Field 7 Code		
UDF7_DESCR	User Defined Field 7 Description		
UDF8_CD	User Defined Field 8 Code		
UDF8_DESCR	User Defined Field 8 Description		
UDF9_CD	User Defined Field 9 Code		
UDF9_DESCR	User Defined Field 9 Description		
UDF10_CD	User Defined Field 10 Code		

Target Field	Description	Source Field	Transformation Logic
UDF10_DESCR	User Defined Field 10 Description		
Data Load Attributes			
UPDATE_DTTM	Update Date and Time		
DATA_LOAD_DTTM	Data Load Date/Time		This field is populated with the load timestamp value.
DATA_SOURCE_IND	Data Source Indicator	CI_INSTALLATION.ENV _ID	This field is populated with the DSI value on the source product instance configuration. The table is populated as part of the initial setup and the DSI value is extracted from the environment ID of the source system.
JOB_NBR	Job Number		This field is populated with the ODI job execution session number.

**Note**: This bucket dimension is configured as one time load only. For information about data reload, see the **Reloading the Bucket Configuration** section in *Oracle Utilities Analytics Warehouse Installation*and Configuration Guide.

#### **Crew Shift**

Includes the details of all crew shifts defined in the Oracle Utilities Extractors and Schema for Oracle Utilities Mobile Workforce Management system.

# **Properties**

Property	Value
Target Table	CD_CREW_SHIFT
Table Type	Dimension
SCD Type	Type 2
Source System Driver Table	M1_CREW_SHFT F1_BUS_OBJ
Stage Table	STG_CD_CREW_SHIFT
ODI Package	B1_PKG_CD_CREW_SHIFT
ETL View	B1_D_CREW_SHIFT_VW

Target Field	Description	Source Field	Transformation Logic
Surrogate Key			
CREW_SHIFT_KEY	Crew Shift Surrogate Key		This field is populated from the SPL_CREW_SHIFT_SEQ sequence.
Natural Keys			
SRC_CREW_SHIFT_ID	Crew Shift ID	M1_CREW_SHFT.CREW_ SHFT_ID	
Attributes			
CREW_SHIFT_TYPE_DE SCR	Crew Shift Type Description	M1_CREW_SHFT_TYPE_ L.DESCR	
PRIMARY_FN_DESCR	Primary Function Description	M1_SVC_CLS_L.DESCR	
CREW_SHIFT_INFO	Crew Shift Description	M1_RESRC_ID.RESRC_I D_VAL	This field is a concatenation of crew name, crew shift type,
		M1_CREW_SHFT_TYPE_ L.DESCR	planned start date, planned end date, and shift status.
		M1_CREW_SHFT.PLAN_ START_DTTM	
		M1_CREW_SHFT.PLAN_ END_DTTM	
		F1_BUS_OBJ_STATUS_L. DESCR	
CREW_SHIFT_TYPE_CD	Crew Shift Type Code	M1_CREW_SHFT.CREW_ SHFT_TYPE_CD	

Target Field	Description	Source Field	Transformation Logic
PRIMARY_FN_CD	Primary Function Code	M1_CREW_SHFT_SVC_C LS.SVC_CLS_CD	This field is populated from the Crew Shift Service Class table based on the usage flag (set as 'Primary') associated with the current shift ID.
User Defined Attributes			
UDF1_CD	Shift Type		
UDF1_DESCR	Shift Type Code		
UDF2_CD	User Defined Field 2 Code		
UDF2_DESCR	User Defined Field 2 Description		
UDF3_CD	User Defined Field 3 Code		
UDF3_DESCR	User Defined Field 3 Description		
UDF4_CD	User Defined Field 4 Code		
UDF4_DESCR	User Defined Field 4 Description		
UDF5_CD	User Defined Field 5 Code		
UDF5_DESCR	User Defined Field 5 Description		
UDF6_CD	User Defined Field 6 Code		
UDF6_DESCR	User Defined Field 6 Description		
UDF7_CD	User Defined Field 7Code		
UDF7_DESCR	User Defined Field 7 Description		
UDF8_CD	User Defined Field 8 Code		
UDF8_DESCR	User Defined Field 8 Description		
UDF9_CD	User Defined Field 9 Code		
UDF9_DESCR	User Defined Field 9 Description		
UDF10_CD	User Defined Field 10 Code		
UDF10_DESCR	User Defined Field 10 Description		
Data Load Attributes			
EFF_END_DTTM	Effective End Date/Time		

Target Field	Description	Source Field	Transformation Logic
EFF_START_DTTM	Effective Start Date/Time		
DATA_LOAD_DTTM	Data Load Date/Time		This field is populated with the load timestamp value.
DATA_SOURCE_IND	Data Source Indicator	CI_INSTALLATION.ENV _ID	This field is populated with the DSI value on the source product instance configuration. The table is populated as part of the initial setup and the DSI value is extracted from the environment ID of the source system.
JOB_NBR	Job Number		This field is populated with the ODI job execution session number.

### **Crew Time Usage**

Holds all valid values for crew time usages based on the tasks carried out by crews. The crew time usages are further classified as productive or non productive.

#### **Properties**

Property	Value
Target Table	CD_CREW_TM_USG
Table Type	Dimension
SCD Type	Type 1
Source System Driver Table	F1_EXT_LOOKUP_VAL
Stage Table	STG_CD_CREW_TM_USG
ODI Package	B1_PKG_CD_CREW_TM_USG
ETL View	B1_D_CREW_TM_USG_VW

Target Field	Description	Source Field	Transformation Logic
Surrogate Key			
CREW_TM_USG_KEY	Crew Time Usage Dimension Surrogate Key		This field is populated from the OUBI_CREW_TM_USG_SE Q sequence.

Target Field	Description	Source Field	Transformation Logic
Natural Keys			
CREW_TM_USG_CD	Crew Time Usage Code	F1_EXT_LOOKUP_VAL. F1_EXT_LOOKUP_VAL UE	This field extracts the records defined only for the M1-CrewTimeUsageLookup lookup business object.
Attributes			
CREW_TM_USG_DESCR	Crew Time Usage Description	F1_EXT_LOOKUP_VAL_ L.DESCR_OVRD	If override description is not available, regular description is extracted.
		F1_EXT_LOOKUP_VAL_ L.DESCR	
PRODUCTIVITY_DESCR	Productivity Description	CI_LOOKUP_VAL_L.DE SCR_OVRD	This field is populated with description from the Lookup
		CI_LOOKUP_VAL_L.DE SCR	Language table for the M1_CREW_TM_USG_CLS_FLG lookup field.
			If override description is not available, regular description is extracted.
PRODUCTIVITY_CD	Productivity Code	F1_EXT_LOOKUP_VAL. BO_DATA_AREA	This field is populated with the productivity code from the CLOB column.
User Defined Attributes			
UDF1_CD	User Defined Field 1 Code		
UDF1_DESCR	User Defined Field 1 Description		
UDF2_CD	User Defined Field 2 Code		
UDF2_DESCR	User Defined Field 2 Description		
UDF3_CD	User Defined Field 3 Code		
UDF3_DESCR	User Defined Field 3 Description		
UDF4_CD	User Defined Field 4 Code		
UDF4_DESCR	User Defined Field 4 Description		
UDF5_CD	User Defined Field 5 Code		
UDF5_DESCR	User Defined Field 5 Description		
UDF6_CD	User Defined Field 6 Code		

Target Field	Description	Source Field	Transformation Logic
UDF6_DESCR	User Defined Field 6 Description		
UDF7_CD	User Defined Field 7Code		
UDF7_DESCR	User Defined Field 7 Description		
UDF8_CD	User Defined Field 8 Code		
UDF8_DESCR	User Defined Field 8 Description		
UDF9_CD	User Defined Field 9 Code		
UDF9_DESCR	User Defined Field 9 Description		
UDF10_CD	User Defined Field 10 Code		
UDF10_DESCR	User Defined Field 10 Description		
Data Load Attributes			
UPDATE_DTTM	Update Date/Time		
DATA_LOAD_DTTM	Data Load Date/Time		This field is populated with the load timestamp value.
DATA_SOURCE_IND	Data Source Indicator	CI_INSTALLATION.ENV _ID	This field is populated with the DSI value on the source product instance configuration. The table is populated as part of the initial setup and the DSI value is extracted from the environment ID of the source system.
JOB_NBR	Job Number		This field is populated with the ODI job execution session number.

# **Early Logoff Time**

Stores the time ranges (in minutes) indicating by how much time the crew is logging off the shift earlier than planned.

# **Properties**

Property	Value
Target Table	CD_EARLY_LOGOFF_TM
Table Type	Dimension
SCD Type	Type 1
Source System Driver Table	F1_BKT_CONFIG
Stage Table	STG_CD_EARLY_LOGOFF_TM
ODI Package	B1_PKG_CD_EARLY_LOGOFF_TM
ETL View	B1_D_EARLY_LOGOFF_TM_VW

Target Field	Description	Source Field	Transformation Logic
Surrogate Key			
EARLY_LOGOFF_TM_ KEY	Early Logoff Time Dimension Surrogate Key		This field is populated from the OUBI_EARLY_LOGOFF_T M_SEQ sequence.
Natural Keys			
START_RANGE	Early Logoff Time Start Range	F1_BKT_CONFIG_VAL.B KT_START_RANGE	The field is populated with the bucket start range based on bucket configuration code.
			The bucket configuration code from the Bucket Configuration table is retrieved based on the bucket configuration BO defined for early logoff time.
END_RANGE	Early Logoff Time End Ran	F1_BKT_CONFIG_VAL.B KT_END_RANGE	The field is populated with the bucket end range based on bucket configuration code.
			The bucket configuration code from the Bucket Configuration table is retrieved based on the bucket configuration BO defined for early log off time.
Attributes			
EARLY_LOGOFF_TM_ DESCR	Early Logoff Time Description	F1_BKT_CONFIG_VAL_ L.DESCR	
CONSIDERED_ONTIME _CD	Considered On Time Code	F1_BKT_CONFIG_VAL.B KT_VAL_TYPE_CD	

Target Field	Description	Source Field	Transformation Logic
CONSIDERED_ONTIME _DESCR	Considered On Time Description	CI_LOOKUP_VAL_L. DESCR_OVRD	This field is populated with description from the Lookup
		CI_LOOKUP_VAL_L. DESCR	Language table for the M1_CONSD_ON_TIME_FL G lookup field.
			If override description is not available, regular description is extracted.
EARLY_LOGOFF_TM_ CD	Early Logoff Time Code		Note: This field is obsolete and is not be populated. The new bucket configurations based on the OUAF bucket configuration tables do not need this.
User Defined Attributes			
UDF1_CD	User Defined Field 1 Code		
UDF1_DESCR	User Defined Field 1 Description		
UDF2_CD	User Defined Field 2 Code		
UDF2_DESCR	User Defined Field 2 Description		
UDF3_CD	User Defined Field 3 Code		
UDF3_DESCR	User Defined Field 3 Description		
UDF4_CD	User Defined Field 4 Code		
UDF4_DESCR	User Defined Field 4 Description		
UDF5_CD	User Defined Field 5 Code		
UDF5_DESCR	User Defined Field 5 Description		
UDF6_CD	User Defined Field 6 Code		
UDF6_DESCR	User Defined Field 6 Description		
UDF7_CD	User Defined Field 7Code		
UDF7_DESCR	User Defined Field 7 Description		
UDF8_CD	User Defined Field 8 Code		
UDF8_DESCR	User Defined Field 8 Description		
UDF9_CD	User Defined Field 9 Code		

Target Field	Description	Source Field	Transformation Logic
UDF9_DESCR	User Defined Field 9 Description		
UDF10_CD	User Defined Field 10 Code		
UDF10_DESCR	User Defined Field 10 Description		
Data Load Attributes			
UPDATE_DTTM	Update Date/Time		
DATA_LOAD_DTTM	Data Load Date/Time		This field is populated with the load timestamp value.
DATA_SOURCE_IND	Data Source Indicator	CI_INSTALLATION.ENV _ID	This field is populated with the DSI value on the source product instance configuration. The table is populated as part of the initial setup and the DSI value is extracted from the environment ID of the source system.
JOB_NBR	Job Number		This field is populated with the ODI job execution session number.

**Note**: This bucket dimension is configured as one time load only. For information about data reload, see **Reloading the Bucket Configuration** section in the *Oracle Utilities Analytics Warehouse Installation and Configuration Guide*.

# **Late Logon Time**

Stores the time ranges (in minutes) indicating by how much time the crew is late to logon for their shift.

#### **Properties**

Property	Value
Target Table	CD_LATE_LOGON_TM
Table Type	Dimension
SCD Type	Type 1
Source System Driver Table	F1_BKT_CONFIG
Stage Table	STG_CD_LATE_LOGON_TM
ODI Package	B1_PKG_CD_LATE_LOGON_TM
ETL View	B1_D_LATE_LOGON_TM_VW

Target Field	Description	Source Field	Transformation Logic
Surrogate Key			
LATE_LOGON_TM_KEY	Late Logon Time Dimension Surrogate Key		This field is populated from the OUBI_LATE_LOGON_TM_SEQ sequence.
Natural Keys			
START_RANGE	Late Logon Time Start Range	F1_BKT_CONFIG_VAL.B KT_START_RANGE	The field is populated with the bucket start range based on bucket configuration code.
			The bucket configuration code from the Bucket Configuration table is retrieved based on the bucket configuration BO defined for late logon time.
END_RANGE	Late Logon Time End Range	F1_BKT_CONFIG_VAL.B KT_END_RANGE	The field is populated with the bucket end range based on bucket configuration code.
			The bucket configuration code from the Bucket Configuration table is retrieved based on the bucket configuration BO defined for late logon time.
Attributes			

Target Field	Description	Source Field	Transformation Logic
LATE_LOGON_TM_DES CR	Late Logon Time Description	F1_BKT_CONFIG_VAL_ L.DESCR	
CONSIDERED_ONTIME _CD	Considered On Time Code	F1_BKT_CONFIG_VAL.B KT_VAL_TYPE_CD	
CONSIDERED_ONTIME _DESCR	Considered On Time Description	CI_LOOKUP_VAL_L.DE SCR_OVRD CI_LOOKUP_VAL_L.DE SCR	This field is populated with description from the Lookup Language table for the M1_CONSD_ON_TIME_FL G lookup field.
			If override description is not available, regular description is extracted.
LATE_LOGON_TM_CD	Late Logon Time Code		Note: This field is obsolete now and is not populated. The new bucket configurations based on the OUAF bucket configuration tables do not need this.
User Defined Attributes			
UDF1_CD	User Defined Field 1 Code		
UDF1_DESCR	User Defined Field 1 Description		
UDF2_CD	User Defined Field 2 Code		
UDF2_DESCR	User Defined Field 2 Description		
UDF3_CD	User Defined Field 3 Code		
UDF3_DESCR	User Defined Field 3 Description		
UDF4_CD	User Defined Field 4 Code		
UDF4_DESCR	User Defined Field 4 Description		
UDF5_CD	User Defined Field 5 Code		
UDF5_DESCR	User Defined Field 5 Description		
UDF6_CD	User Defined Field 6 Code		
UDF6_DESCR	User Defined Field 6 Description		
UDF7_CD	User Defined Field 7Code		
UDF7_DESCR	User Defined Field 7 Description		

Target Field	Description	Source Field	Transformation Logic
UDF8_CD	User Defined Field 8 Code		
UDF8_DESCR	User Defined Field 8 Description		
UDF9_CD	User Defined Field 9 Code		
UDF9_DESCR	User Defined Field 9 Description		
UDF10_CD	User Defined Field 10 Code		
UDF10_DESCR	User Defined Field 10 Description		
Data Load Attributes			
UPDATE_DTTM	Update Date/Time		
DATA_LOAD_DTTM	Data Load Date/Time		This field is populated with the load timestamp value.
DATA_SOURCE_IND	Data Source Indicator	CI_INSTALLATION.ENV _ID	This field is populated with the DSI value on the source product instance configuration. The table is populated as part of the initial setup and the DSI value is extracted from the environment ID of the source system.
JOB_NBR	Job Number		This field is populated with the ODI job execution session number.

**Note**: This bucket dimension is configured as one time load only. For information about data reload, see **Reloading the Bucket Configuration** section in the *Oracle Utilities Analytics Warehouse Installation and Configuration Guide*.

# **Response Time Deviation**

Stores the configurable ranges (in minutes) for the deviations in the response time of crews against the SLAs defined for various activities. It has an indicator to tell if the SLA is met or missed.

#### **Properties**

Property	Value
Target Table	CD_RESP_TM_DEV
Table Type	Dimension
SCD Type	Type 1
Source System Driver Table	F1_BKT_CONFIG
Stage Table	STG_CD_RESP_TM_DEV
ODI Package	B1_PKG_CD_RESP_TM_DEV
ETL View	B1_D_RESP_TM_DEV_VW

Target Field	Description	Source Field	Transformation Logic
Surrogate Key			
RESP_TM_DEV_KEY	Response Time Deviation Dimension Surrogate Key		This field is populated from the OUBI_RESP_TM_DEV_SE Q sequence.
Natural Keys			-
START_RANGE	Response Time Deviation Start Range	F1_BKT_CONFIG_VAL.B KT_START_RANGE	The field is populated with the bucket start range based on bucket configuration code.
			The bucket configuration code from the Bucket Configuration table is retrieved based on the bucket configuration BO defined for response time deviation.

Target Field	Description	Source Field	Transformation Logic
END_RANGE	Response Time Deviation End Range	F1_BKT_CONFIG_VAL.B KT_END_RANGE	The field is populated with the bucket end range based on bucket configuration code.
			The bucket configuration code from the Bucket Configuration table is retrieved based on the bucket configuration BO defined for response time deviation.
Attributes			
RESP_TM_DEV_DESCR	Response Time Deviation Description	F1_BKT_CONFIG_VAL_ L.DESCR	
SLA_STATUS_DESCR	SLA Status Description	CI_LOOKUP_VAL_L.DE SCR_OVRD	This field is populated with description from the Lookup Language table for the
		CI_LOOKUP_VAL_L.DE SCR	M1_SLA_STATUS_FLG lookup field.
			If override description is not available, regular description is extracted.
SLA_STATUS_CD	SLA Status Code	F1_BKT_CONFIG_VAL.B KT_VAL_TYPE_CD	
RESP_TM_DEV_CD	Response Time Deviation Code		Note: This field is obsolete and is not populated. The new bucket configurations based on the OUAF bucket configuration tables do not need this.
User Defined Attributes			
UDF1_CD	User Defined Field 1 Code		
UDF1_DESCR	User Defined Field 1 Description		
UDF2_CD	User Defined Field 2 Code		
UDF2_DESCR	User Defined Field 2 Description		
UDF3_CD	User Defined Field 3 Code		
UDF3_DESCR	User Defined Field 3 Description		
UDF4_CD	User Defined Field 4 Code		
UDF4_DESCR	User Defined Field 4 Description		

Target Field	Description	Source Field	Transformation Logic
UDF5_CD	User Defined Field 5 Code		
UDF5_DESCR	User Defined Field 5 Description		
UDF6_CD	User Defined Field 6 Code		
UDF6_DESCR	User Defined Field 6 Description		
UDF7_CD	User Defined Field 7Code		
UDF7_DESCR	User Defined Field 7 Description		
UDF8_CD	User Defined Field 8 Code		
UDF8_DESCR	User Defined Field 8 Description		
UDF9_CD	User Defined Field 9 Code		
UDF9_DESCR	User Defined Field 9 Description		
UDF10_CD	User Defined Field 10 Code		
UDF10_DESCR	User Defined Field 10 Description		
Data Load Attributes			
UPDATE_DTTM	Update Date/Time		
DATA_LOAD_DTTM	Data Load Date/Time		This field is populated with the load timestamp value.
DATA_SOURCE_IND	Data Source Indicator	CI_INSTALLATION.ENV _ID	This field is populated with the DSI value on the source product instance configuration. The table is populated as part of the initial setup and the DSI value is extracted from the environment ID of the source system.
JOB_NBR	Job Number		This field is populated with the ODI job execution session number.

**Note**: This bucket dimension is configured as one time load only. For information about data reload, see **Reloading the Bucket Configuration** section in the *Oracle Utilities Analytics Warehouse Installation and Configuration Guide*.

#### **Shift BO Status**

Holds valid combination of status and reason for shifts.

#### **Properties**

Property	Value
Target Table	CD_SHIFT_BO_STATUS
Table Type	Dimension
SCD Type	Type 1
Source System Driver Table	F1_BUS_OBJ F1_BUS_OBJ_STATUS_RSN
Stage Table	STG_CD_SHIFT_BO_STATUS
ODI Package	B1_PKG_CD_SHIFT_BO_STATUS
ETL View	B1_D_SHIFT_BO_STATUS_VW

Target Field	Description	Source Field	Transformation Logic
Surrogate Key			
SHIFT_BO_STATUS_KEY	Shift BO Status Surrogate Key		This field is populated from the OUBI_SHIFT_BO_STAT_SE Q sequence.
Natural Keys			
BUS_OBJ_CD	Business Object	F1_BUS_OBJ.BUS_OBJ_C D	This field extracts all business objects of the Crew Shift maintenance object only.
STATUS_CD	BO Status Code	F1_BUS_OBJ_STATUS.B O_STATUS_CD	
REASON_CD	Status Reason Code	F1_BUS_OBJ_STATUS_R SN.BO_STATUS_REASO N_CD	
Attributes			
BUS_OBJ_DESCR	Business Object Description	F1_BUS_OBJ_L.DESCR	
STATUS_DESCR	Status Description	F1_BUS_OBJ_STATUS_L. DESCR	
STATUS_COND_CD	Status Condition Code	F1_BUS_OBJ_STATUS.B O_STATUS_COND_FLG	

Target Field	Description	Source Field	Transformation Logic
STATUS_COND_DESCR	Status Condition Description	CI_LOOKUP_VAL_L.NV L(CI_LOOKUP_VAL_L.D ESCR_OVRD,CI_LOOKU P_VAL_L.DESCR)	This field is populated with description from the Lookup Language table for the BO_STATUS_COND_FLG lookup field.
			If override description is not available, regular description is extracted.
REASON_DESCR	Status Reason Description	F1_BUS_OBJ_STATUS_R SN_L.DESCR	
User Defined Attributes			
UDF1_CD	User Defined Field 1 Code		
UDF1_DESCR	User Defined Field 1 Description		
UDF2_CD	User Defined Field 2 Code		
UDF2_DESCR	User Defined Field 2 Description		
UDF3_CD	User Defined Field 3 Code		
UDF3_DESCR	User Defined Field 3 Description		
UDF4_CD	User Defined Field 4 Code		
UDF4_DESCR	User Defined Field 4 Description		
UDF5_CD	User Defined Field 5 Code		
UDF5_DESCR	User Defined Field 5 Description		
UDF6_CD	User Defined Field 6 Code		
UDF6_DESCR	User Defined Field 6 Description		
UDF7_CD	User Defined Field 7Code		
UDF7_DESCR	User Defined Field 7 Description		
UDF8_CD	User Defined Field 8 Code		
UDF8_DESCR	User Defined Field 8 Description		
UDF9_CD	User Defined Field 9 Code	<u></u>	<del></del>
UDF9_DESCR	User Defined Field 9 Description		
UDF10_CD	User Defined Field 10 Code		

Target Field	Description	Source Field	Transformation Logic
UDF10_DESCR	User Defined Field 10 Description		
Data Load Attributes			
UPDATE_DTTM	Update Date/Time		
DATA_LOAD_DTTM	Data Load Date/Time		This field is populated with the load timestamp value.
DATA_SOURCE_IND	Data Source Indicator	CI_INSTALLATION.ENV _ID	This field is populated with the DSI value on the source product instance configuration. The table is populated as part of the initial setup and the DSI value is extracted from the environment ID of the source system.
JOB_NBR	Job Number		This field is populated with the ODI job execution session number.

#### **Task BO Status**

Holds all valid combination of status and reasons for schedulable tasks.

#### **Properties**

Property	Value
Target Table	CD_TASK_BO_STATUS
Table Type	Dimension
SCD Type	Type 1
Source System Driver Table	F1_BUS_OBJ F1_BUS_OBJ_STATUS_RSN
Stage Table	STG_CD_TASK_BO_STATUS
ODI Package	B1_PKG_CD_TASK_BO_STATUS
ETL View	B1_D_TASK_BO_STATUS_VW

Target Field	Description	Source Field	Transformation Logic
Surrogate Key			

Target Field	Description	Source Field	Transformation Logic
TASK_BO_STATUS_KEY	Task BO Status Surrogate Key		This field is populated from the OUBI_TASK_BO_STAT_SE Q sequence.
Natural Keys			
BUS_OBJ_CD	Business Object	F1_BUS_OBJ.BUS_OBJ_C D	This field extracts all business objects of the Device Event maintenance object only.
STATUS_CD	BO Status Code	F1_BUS_OBJ_STATUS.B O_STATUS_CD	
REASON_CD	Status Reason Code	F1_BUS_OBJ_STATUS_R SN.BO_STATUS_REASO N_CD	
Attributes			
BUS_OBJ_DESCR	Business Object Description	F1_BUS_OBJ_L.DESCR	
STATUS_DESCR	Status Description	F1_BUS_OBJ_STATUS_L. DESCR	
STATUS_COND_CD	Status Condition Code	F1_BUS_OBJ_STATUS.B O_STATUS_COND_FLG	
STATUS_COND_DESCR	Status Condition Description	CI_LOOKUP_VAL_L.NV L(CI_LOOKUP_VAL_L.D ESCR_OVRD,CI_LOOKU P_VAL_L.DESCR)	This field is populated with description from the Lookup Language table for the BO_STATUS_COND_FLG lookup field.
			If override description is not available, regular description is extracted.
REASON_DESCR	Status Reason Description	F1_BUS_OBJ_STATUS_R SN_L.DESCR	
INCOMPLETE_IND	Incomplete Indicator	F1_BUS_OBJ_STATUS_O PT.BO_OPT_VAL	This field is populated based on the state condition defined on the business object status.
			If the status is 'Postponed', or 'Completed' with 'Incomplete' status reason, the indicator is populated as '1', else '0'.
User Defined Attributes			
UDF1_CD	User Defined Field 1 Code		
UDF1_DESCR	User Defined Field 1 Description		
UDF2_CD	User Defined Field 2 Code		

Target Field	Description	Source Field	Transformation Logic
UDF2_DESCR	User Defined Field 2 Description		
UDF3_CD	User Defined Field 3 Code		
UDF3_DESCR	User Defined Field 3 Description		
UDF4_CD	User Defined Field 4 Code		
UDF4_DESCR	User Defined Field 4 Description		
UDF5_CD	User Defined Field 5 Code		
UDF5_DESCR	User Defined Field 5 Description		
UDF6_CD	User Defined Field 6 Code		
UDF6_DESCR	User Defined Field 6 Description		
UDF7_CD	User Defined Field 7Code		
UDF7_DESCR	User Defined Field 7 Description		
UDF8_CD	User Defined Field 8 Code		
UDF8_DESCR	User Defined Field 8 Description		
UDF9_CD	User Defined Field 9 Code		
UDF9_DESCR	User Defined Field 9 Description		
UDF10_CD	User Defined Field 10 Code		
UDF10_DESCR	User Defined Field 10 Description		
Data Load Attributes			
UPDATE_DTTM	Update Date/Time		
DATA_LOAD_DTTM	Data Load Date/Time		This field is populated with the load timestamp value.
DATA_SOURCE_IND	Data Source Indicator	CI_INSTALLATION.ENV _ID	This field is populated with the DSI value on the source product instance configuration. The table is populated as part of the initial setup and the DSI value is extracted from the environment ID of the source system.

Target Field	Description	Source Field	Transformation Logic
JOB_NBR	Job Number		This field is populated with the ODI job execution session number.

# Task Type

Holds all task types defined in the Oracle Utilities Extractors and Schema for Oracle Utilities Mobile Workforce Management system along with their class, priority, service type, and SLA details.

#### **Properties**

Property	Value
Target Table	CD_TASK_TYPE
Table Type	Dimension
SCD Type	Type 1
Source System Driver Table	M1_TASK_TYPE
Stage Table	STG_CD_TASK_TYPE
ODI Package	B1_PKG_CD_TASK_TYPE
ETL View	B1_D_TASK_TYPE_VW

Target Field	Description	Source Field	Transformation Logic
Surrogate Key			
TASK_TYPE_KEY	Task Type Dimension Surrogate Key		This field is populated from the OUBI_TASK_TYPE_SEQ sequence.
Natural Keys			
TASK_TYPE_CD	Activity Type Code	M1_TASK_TYPE.TASK_ TYPE_CD	
Attributes			
TASK_TYPE_DESCR	Task Type Description	M1_TASK_TYPE_L.DES CR	

Target Field	Description	Source Field	Transformation Logic
TASK_CLASS_CD	Task Class Code	M1_TASK_TYPE.TASK_ CLS_FLG	
PRIORITY_PROF_CD	Priority Profile Code	M1_TASK_TYPE.PRI_PR OF_CD	
SVC_CATEGORY_CD	Service Category Code	M1_TASK_TYPE.BO_DA TA_AREA	This field is populated with the service category code from the CLOB column.
TASK_CLASS_DESCR	Task Class Description	CI_LOOKUP_VAL_L.DE SCR_OVRD	This field is populated with description from the Lookup Language table for the
		CI_LOOKUP_VAL_L.DE SCR	TASK_CLS_FLG lookup field.
			If override description is not available, regular description is extracted.
PRIORITY_PROF_DESCR	Priority Profile Description	M1_PRI_PROF_L.DESCR	
SVC_CATEGORY_DESCR	Service Category Description	F1_EXT_LOOKUP_VAL_ L.DESCR_OVRD	This field is populated with description from the Lookup Language table for the M1-
		F1_EXT_LOOKUP_VAL_ L.DESCR	ServiceCategoryLookup lookup business object.
			If override description is not available, regular description is extracted.
RESP_TM_SLA	Response Time SLA	M1_TASK_TYPE.BO_DA TA_AREA	This field is populated with the response time SLA from the CLOB column.
User Defined Attributes			
UDF1_CD	User Defined Field 1 Code		
UDF1_DESCR	User Defined Field 1 Description		
UDF2_CD	User Defined Field 2 Code		
UDF2_DESCR	User Defined Field 2 Description		
UDF3_CD	User Defined Field 3 Code		
UDF3_DESCR	User Defined Field 3 Description		
UDF4_CD	User Defined Field 4 Code		
UDF4_DESCR	User Defined Field 4 Description		
UDF5_CD	User Defined Field 5 Code		

Target Field	Description	Source Field	Transformation Logic
UDF5_DESCR	User Defined Field 5 Description		
UDF6_CD	User Defined Field 6 Code		
UDF6_DESCR	User Defined Field 6 Description		
UDF7_CD	User Defined Field 7Code		
UDF7_DESCR	User Defined Field 7 Description		
UDF8_CD	User Defined Field 8 Code		
UDF8_DESCR	User Defined Field 8 Description		
UDF9_CD	User Defined Field 9 Code		
UDF9_DESCR	User Defined Field 9 Description		
UDF10_CD	User Defined Field 10 Code		
UDF10_DESCR	User Defined Field 10 Description		
Data Load Attributes			
UPDATE_DTTM	Update Date/Time		
DATA_LOAD_DTTM	Data Load Date/Time		This field is populated with the load timestamp value.
DATA_SOURCE_IND	Data Source Indicator	CI_INSTALLATION.ENV _ID	This field is populated with the DSI value on the source product instance configuration. The table is populated as part of the initial setup and the DSI value is extracted from the environment ID of the source system.
JOB_NBR	Job Number		This field is populated with the ODI job execution session number.

### **Travel Distance Deviation**

Stores the percentage ranges for deviations of actual distance relative to estimated distance traveled by the crew.

# **Properties**

Property	Value
Target Table	CD_TRAVEL_DIST_DEV
Table Type	Dimension
SCD Type	Type 1
Source System Driver Table	F1_BKT_CONFIG
Stage Table	STG_CD_TRAVEL_DIST_DEV
ODI Package	B1_PKG_CD_TRAVEL_DIST_DEV
ETL View	B1_D_TRAVEL_DIST_DEV_VW

Target Field	Description	Source Field	Transformation Logic
Surrogate Key			
TRAVEL_DIST_DEV_ KEY	Travel Distance Deviation Dimension Surrogate Key		This field is populated from the OUBI_TRAVEL_DIST_DEV _SEQ sequence.
Natural Keys			
START_RANGE	Travel Distance Deviation Start Range	F1_BKT_CONFIG_VAL.B KT_START_RANGE	This field is populated with the bucket start range based on bucket configuration code.
			The bucket configuration code from the Bucket Configuration table is retrieved based on the bucket configuration BO defined for travel distance deviation.
END_RANGE	Travel Distance Deviation End Range	F1_BKT_CONFIG_VAL.B KT_END_RANGE	This field is populated with the bucket end range based on bucket configuration code.
			The bucket configuration code from the Bucket Configuration table is retrieved based on the bucket configuration BO defined for travel distance deviation.
Attributes			
TRAVEL_DIST_DEV_ DESCR	Travel Distance Deviation Description	F1_BKT_CONFIG_VAL_ L.DESCR	

Target Field	Description	Source Field	Transformation Logic
TRAVEL_DIST_DEV_CD	Distance Deviation Code		Note: This field is obsolete and is not populated. The new bucket configurations based on the OUAF bucket configuration tables do not need this.
User Defined Attributes			
UDF1_CD	User Defined Field 1 Code		
UDF1_DESCR	User Defined Field 1 Description		
UDF2_CD	User Defined Field 2 Code		
UDF2_DESCR	User Defined Field 2 Description		
UDF3_CD	User Defined Field 3 Code		
UDF3_DESCR	User Defined Field 3 Description		
UDF4_CD	User Defined Field 4 Code		
UDF4_DESCR	User Defined Field 4 Description		
UDF5_CD	User Defined Field 5 Code		
UDF5_DESCR	User Defined Field 5 Description		
UDF6_CD	User Defined Field 6 Code		
UDF6_DESCR	User Defined Field 6 Description		
UDF7_CD	User Defined Field 7Code		
UDF7_DESCR	User Defined Field 7 Description		
UDF8_CD	User Defined Field 8 Code		
UDF8_DESCR	User Defined Field 8 Description		
UDF9_CD	User Defined Field 9 Code		
UDF9_DESCR	User Defined Field 9 Description		
UDF10_CD	User Defined Field 10 Code		
UDF10_DESCR	User Defined Field 10 Description		

Target Field	Description	Source Field	Transformation Logic
Data Load Attributes			
UPDATE_DTTM	Update Date/Time		
DATA_LOAD_DTTM	Data Load Date/Time		This field is populated with the load timestamp value.
DATA_SOURCE_IND	Data Source Indicator	CI_INSTALLATION.ENV _ID	This field is populated with the DSI value on the source product instance configuration. The table is populated as part of the initial setup and the DSI value is extracted from the environment ID of the source system.
JOB_NBR	Job Number		This field is populated with the ODI job execution session number.

**Note**: This bucket dimension is configured as one time load only. For information about data reload, see **Reloading the Bucket Configuration** section in the *Oracle Utilities Analytics Warehouse Installation and Configuration Guide*.

### **Travel Duration Deviation**

Stores the percentage ranges for deviations of actual travel duration relative to estimated travel duration of crews.

#### **Properties**

Property	Value
Target Table	CD_TRAVEL_DUR_DEV
Table Type	Dimension
SCD Type	Type 1
Source System Driver Table	F1_BKT_CONFIG
Stage Table	STG_CD_TRAVEL_DUR_DEV
ODI Package	B1_PKG_CD_TRAVEL_DUR_DEV
ETL View	B1_D_TRAVEL_DUR_DEV_VW

Target Field	Description	Source Field	Transformation Logic
Surrogate Key			

Target Field	Description	Source Field	Transformation Logic
TRAVEL_DUR_DEV_ KEY	Travel Duration Deviation Dimension Surrogate Key		This field is populated from the OUBI_TRAVEL_DUR_DEV _SEQ sequence.
Natural Keys			
START_RANGE	Travel Duration Deviation Start Range	F1_BKT_CONFIG_VAL.B KT_START_RANGE	This field is populated with the bucket start range based on bucket configuration code.
			The bucket configuration code from the Bucket Configuration table is retrieved based on the bucket configuration BO defined for travel duration deviation.
END_RANGE	Travel Duration Deviation End Range	F1_BKT_CONFIG_VAL.B KT_END_RANGE	The field is populated with the bucket end range based on bucket configuration code.
			The bucket configuration code from the Bucket Configuration table is retrieved based on the bucket configuration BO defined for travel duration deviation.
Attributes			
TRAVEL_DUR_DEV_ DESCR	Travel Duration Deviation	F1_BKT_CONFIG_VAL_ L.DESCR	
TRAVEL_DUR_DEV_CD	Travel Duration Deviation Code		Note: This field is obsolete and will not be populated. The new bucket configurations based on the OUAF bucket configuration tables do not need this.
User Defined Attributes			
UDF1_CD	User Defined Field 1 Code		
UDF1_DESCR	User Defined Field 1 Description		
UDF2_CD	User Defined Field 2 Code		
UDF2_DESCR	User Defined Field 2 Description		
UDF3_CD	User Defined Field 3 Code		
UDF3_DESCR	User Defined Field 3 Description		

Target Field	Description	Source Field	Transformation Logic
UDF4_CD	User Defined Field 4 Code		
UDF4_DESCR	User Defined Field 4 Description		
UDF5_CD	User Defined Field 5 Code		
UDF5_DESCR	User Defined Field 5 Description		
UDF6_CD	User Defined Field 6 Code		
UDF6_DESCR	User Defined Field 6 Description		
UDF7_CD	User Defined Field 7Code		
UDF7_DESCR	User Defined Field 7 Description		
UDF8_CD	User Defined Field 8 Code		
UDF8_DESCR	User Defined Field 8 Description		
UDF9_CD	User Defined Field 9 Code		
UDF9_DESCR	User Defined Field 9 Description		
UDF10_CD	User Defined Field 10 Code		
UDF10_DESCR	User Defined Field 10 Description		
Data Load Attributes			
UPDATE_DTTM	Update Date/Time		
DATA_LOAD_DTTM	Data Load Date/Time		This field is populated with the load timestamp value.
DATA_SOURCE_IND	Data Source Indicator	CI_INSTALLATION.ENV _ID	This field is populated with the DSI value on the source product instance configuration. The table is populated as part of the initial setup and the DSI value is extracted from the environment ID of the source system.
JOB_NBR	Job Number		This field is populated with the ODI job execution session number.

**Note**: This bucket dimension is configured as one time load only. For information about data reload, see the **Reloading the Bucket Configuration** section in the *Oracle Utilities Analytics Warehouse Installation and Configuration Guide*.

### **Work Duration Deviation**

Stores the percentage ranges for deviations in actual work duration relative to estimated work duration of activities.

### **Properties**

Property	Value
Target Table	CD_WORK_DUR_DEV
Table Type	Dimension
SCD Type	Type 1
Source System Driver Table	F1_BKT_CONFIG
Stage Table	STG_CD_WORK_DUR_DEV
ODI Package	B1_PKG_CD_WORK_DUR_DEV
ETL View	B1_D_WORK_DUR_DEV_VW

Target Field	Description	Source Field	Transformation Logic
Surrogate Key			
WORK_DUR_DEV_KEY	Work Duration Deviation Dimension Surrogate Key		This field is populated from the OUBI_WORK_DUR_DEV_SEQ sequence.
Natural Keys			
START_RANGE	Work Duration Deviation Start Range	F1_BKT_CONFIG_VAL.B KT_START_RANGE	This field is populated with the bucket start range based on bucket configuration code.
			The bucket configuration code from the Bucket Configuration table is retrieved based on the bucket configuration BO defined for work duration deviation.

Target Field	Description	Source Field	Transformation Logic
END_RANGE	Work Duration Deviation End Range	F1_BKT_CONFIG_VAL.B KT_END_RANGE	The field is populated with the bucket end range based on bucket configuration code.
			The bucket configuration code from the Bucket Configuration table is retrieved based on the bucket configuration BO defined for work duration deviation.
Attributes			
WORK_DUR_DEV_ DESCR	Work Duration Deviation Description	F1_BKT_CONFIG_VAL_ L.DESCR	
WORK_DUR_DEV_CD	Work Duration Deviation Code		Note: This field is obsolete and is not populated. The new bucket configurations based on the OUAF bucket configuration tables do not need this.
User Defined Attributes			
UDF1_CD	User Defined Field 1 Code		
UDF1_DESCR	User Defined Field 1 Description		
UDF2_CD	User Defined Field 2 Code		
UDF2_DESCR	User Defined Field 2 Description		
UDF3_CD	User Defined Field 3 Code		
UDF3_DESCR	User Defined Field 3 Description		
UDF4_CD	User Defined Field 4 Code		
UDF4_DESCR	User Defined Field 4 Description		
UDF5_CD	User Defined Field 5 Code		
UDF5_DESCR	User Defined Field 5 Description		
UDF6_CD	User Defined Field 6 Code		
UDF6_DESCR	User Defined Field 6 Description		
UDF7_CD	User Defined Field 7Code		
UDF7_DESCR	User Defined Field 7 Description		

Target Field	Description	Source Field	Transformation Logic
UDF8_CD	User Defined Field 8 Code		
UDF8_DESCR	User Defined Field 8 Description		
UDF9_CD	User Defined Field 9 Code		
UDF9_DESCR	User Defined Field 9 Description		
UDF10_CD	User Defined Field 10 Code		
UDF10_DESCR	User Defined Field 10 Description		
Data Load Attributes			
UPDATE_DTTM	Update Date/Time		
DATA_LOAD_DTTM	Data Load Date/Time		This field is populated with the load timestamp value.
DATA_SOURCE_IND	Data Source Indicator	CI_INSTALLATION.ENV _ID	This field is populated with the DSI value on the source product instance configuration. The table is populated as part of the initial setup and the DSI value is extracted from the environment ID of the source system.
JOB_NBR	Job Number		This field is populated with the ODI job execution session number.

**Note**: This bucket dimension is configured as one time load only. For information about data reload, see the **Reloading the Bucket Configuration** section in *Oracle Utilities Analytics Warehouse Installation*and Configuration Guide.

## **Shared Dimensions**

The dimensions that are used in the star schemas of other source products as well are called the **shared** dimensions. The other products also populate these shared dimensions with their data. The data source indicator (DSI) column plays a vital role in identifying the records belonging to a specific source product.

#### **Account**

Though Account dimension is referenced in the Oracle Utilities Mobile Workforce Management facts, it is populated only by the Oracle Utilities Customer Care and Billing source product. The ETL processes of the Oracle Utilities Mobile Workforce Management facts map this dimension based on the integration between Oracle Utilities Mobile Workforce Management and Oracle Utilities Customer Care and Billing.

Since this dimension is not populated by Oracle Utilities Mobile Workforce Management, the source mapping details are not provided in the document. See the *Oracle Utilities Extractors and Schema for Oracle Utilities Customer Care and Billing* for the mapping details.

#### **Address**

Includes a record for every address (such as location, task, POU, and resources) defined in the Oracle Utilities Mobile Workforce Management system.

This dimension is also populated by Oracle Utilities Operational Device Management, Oracle Utilities Meter Data Management, Oracle Utilities Customer Care and Billing, Oracle Utilities Network Management System, and Oracle Utilities Work and Asset Management.

# **Properties**

Property	Value
Target Table	CD_ADDR
Table Type	Dimension
SCD Type	Type 2
Source System Driver Table	M1_TASK_ADDR M1_LOCATION M1_POU M1_RESRC
Stage Table	STG_CD_ADDR
ODI Package	B1_PKG_CD_ADDR
ETL View	B1_D_ADDR_VW

#### **Fields**

### Source 1 - Task Address (M1\_TASK ADDR)

Target Field	Description	Source Field	Transformation Logic
Surrogate Key			
ADDR_KEY	Address Dimension Surrogate Key		This field is populated from the SPL_ADDR_SEQ sequence.

Target Field	Description	Source Field	Transformation Logic
Natural Keys			
SRC_ADDR_ID	Premise ID	M1_TASK_ADDR.ADDR ESS1	This natural key is the concatenation of all address
		M1_TASK_ADDR.ADDR ESS2	attributes, in uppercase.
		M1_TASK_ADDR.ADDR ESS3	
		M1_TASK_ADDR.ADDR ESS4	
		M1_TASK_ADDR.CROSS _STREET	
		M1_TASK_ADDR.SUBUR B	
		M1_TASK_ADDR.CITY	
		M1_TASK_ADDR.COUN TY	
		M1_TASK_ADDR.STATE	
		M1_TASK_ADDR.POSTA L M1_TASK_ADDR.COUN TRY	
Attributes			
ADDR_LINE1	Address Line 1	M1_TASK_ADDR.ADDR ESS1	
ADDR_LINE2	Address Line 2	M1_TASK_ADDR.ADDR ESS2	
ADDR_LINE3	Address Line 3	M1_TASK_ADDR.ADDR ESS3	
ADDR_LINE4	Address Line 4	M1_TASK_ADDR.ADDR ESS4	
ADDR_INFO	Address Information	M1_TASK_ADDR.ADDR ESS1	This field is populated from the Task Address table based on the concatenation of the
		M1_TASK_ADDR.CITY	address, city, state, and postal code.
		M1_TASK_ADDR.STATE	
		M1_TASK_ADDR.POSTA L	

Target Field	Description	Source Field	Transformation Logic
CITY	City	M1_TASK_ADDR.UPPER (CITY)	
COUNTY	County	M1_TASK_ADDR.COUN TY	
POSTAL	Postal Code	M1_TASK_ADDR.POSTA L	
STATE_DESCR	State Description	CI_STATE_L.DESCR	
COUNTRY_DESCR	Country Description	CI_COUNTRY_L.DESCR	
CROSS_STREET	Cross Street	M1_TASK_ADDR.CROSS _STREET	
SUBURB	Suburb	M1_TASK_ADDR.SUBUR B	
STATE_CD	State Code	M1_TASK_ADDR.STATE	
COUNTRY_CD	Country Code	M1_TASK_ADDR.COUN TRY	
GEO_CODE	Geographical Code		
User Defined Attributes			
UDF1_CD	City Code	M1_TASK_ADDR.UPPER (CITY)	
UDF1_DESCR	City Description	M1_TASK_ADDR.UPPER (CITY)	
UDF2_CD	County Code	M1_TASK_ADDR.COUN TY	
UDF2_DESCR	County Description	M1_TASK_ADDR.COUN TY	
UDF3_CD	Postal Code	M1_TASK_ADDR.POSTA L	
UDF3_DESCR	Postal Code	M1_TASK_ADDR.POSTA L	
UDF4_CD	State Code	M1_TASK_ADDR.STATE	
UDF4_DESCR	State Description	CI_STATE_L.DESCR	
UDF5_CD	Country Code	M1_TASK_ADDR.COUN TRY	
UDF5_DESCR	Country Description	CI_COUNTRY_L.DESCR	
UDF6_CD	Geo Code Value		
UDF6_DESCR	Geo Code		
UDF7_CD	Premise Char 1 Code		
UDF7_DESCR	Premise Char 1		

Target Field	Description	Source Field	Transformation Logic
UDF8_CD	Premise Char 2 Code		
UDF8_DESCR	Premise Char 2		
UDF9_CD	Premise Char 3 Code		
UDF9_DESCR	Premise Char 3		
UDF10_CD	Premise Char 4 Code		
UDF10_DESCR	Premise Char 4 Code		
UDF11_CD	User Defined Field 11 Code		
UDF11_DESCR	User Defined Field 11 Description		
UDF12_CD	User Defined Field 12 Code		
UDF12_DESCR	User Defined Field 12 Description		
UDF13_CD	User Defined Field 13 Code		
UDF13_DESCR	User Defined Field 13 Description		
UDF14_CD	User Defined Field 14 Code		
UDF14_DESCR	User Defined Field 14 Description		
UDF15_CD	User Defined Field 15 Code		
UDF15_DESCR	User Defined Field 15 Description		
UDF16_CD	User Defined Field 16 Code		
UDF16_DESCR	User Defined Field 16 Description		
UDF1_NUM	User Defined Field 1 Number		
UDF2_NUM	User Defined Field 2 Number		
UDF3_NUM	User Defined Field 3 Number		
UDF4_NUM	User Defined Field 4 Number		
UDF5_NUM	User Defined Field 5 Number		
UDF6_NUM	User Defined Field 6 Number		
UDF7_NUM	User Defined Field 7 Number		

Target Field	Description	Source Field	Transformation Logic
UDF8_NUM	User Defined Field 8 Number		
UDF9_NUM	User Defined Field 9 Number		
UDF10_NUM	User Defined Field 10 Number		
UDF1_DATE	User Defined Field 1 Date		
UDF2_DATE	User Defined Field 2 Date		
UDF3_DATE	User Defined Field 3 Date		
UDF4_DATE	User Defined Field 4 Date		
UDF5_DATE	User Defined Field 5 Date		
UDF6_DATE	User Defined Field 6 Date		
UDF7_DATE	User Defined Field 7 Date		
UDF8_DATE	User Defined Field 8 Date		
UDF9_DATE	User Defined Field 9 Date		
UDF10_DATE	User Defined Field 10 Date		
FLEXFIELD1	Flex Field 1		
FLEXFIELD2	Flex Field 2		
FLEXFIELD3	Flex Field 3		
FLEXFIELD4	Flex Field 4		
FLEXFIELD5	Flex Field 5		
FLEXFIELD6	Flex Field 6		
FLEXFIELD7	Flex Field 7		
FLEXFIELD8	Flex Field 8		
FLEXFIELD9	Flex Field 9		
FLEXFIELD10	Flex Field 10		
Data Load Attributes			
EFF_END_DTTM	Effective End Date/Time		
EFF_START_DTTM	Effective Start Date/Time		
DATA_LOAD_DTTM	Data Load Date/Time		This field is populated with the load timestamp value.

Target Field	Description	Source Field	Transformation Logic
DATA_SOURCE_IND	Data Source Indicator	CI_INSTALLATION.ENV _ID	This field is populated with the DSI value on the source product instance configuration. The table is populated as part of the initial setup and the DSI value is extracted from the environment ID of the source system.
JOB_NBR	Job Number		This field is populated with the ODI job execution session number.

### Source 2 - Location (M1\_LOCATION)

Target Field	Description	Source Field	Transformation Logic
Surrogate Key			
ADDR_KEY	Address Dimension Surrogate Key		This field is populated from the SPL_ADDR_SEQ sequence.
Natural Keys			
SRC_ADDR_ID	Premise ID	M1_LOCATION.ADDRE SS1	This natural key is the concatenation of all address
		M1_LOCATION.ADDRE SS2	attributes, in uppercase.
		M1_LOCATION.ADDRE SS3	
		M1_LOCATION.ADDRE SS4	
		M1_LOCATION.CROSS_ STREET	
		M1_LOCATION.SUBURB	
		M1_LOCATION.CITY	
		M1_LOCATION.COUNT Y	
		M1_LOCATION.STATE	
		M1_LOCATION.POSTAL	
		M1_LOCATION.COUNT RY	

Target Field	Description	Source Field	Transformation Logic
Attributes			
ADDR_LINE1	Address Line 1	M1_LOCATION.ADDRE SS1	
ADDR_LINE2	Address Line 2	M1_LOCATION.ADDRE SS2	
ADDR_LINE3	Address Line 3	M1_LOCATION.ADDRE SS3	
ADDR_LINE4	Address Line 4	M1_LOCATION.ADDRE SS4	
ADDR_INFO	Address Information	M1_LOCATION.ADDRE SS1	This field is populated from the Location table based on the
		M1_LOCATION.CITY	concatenation of the address, city, state, and postal code.
		M1_LOCATION.STATE	
		M1_LOCATION.POSTAL	
CITY	City	M1_LOCATION.UPPER(CITY)	
COUNTY	County	M1_LOCATION.COUNT Y	
POSTAL	Postal Code	M1_LOCATION.POSTAL	
STATE_DESCR	State Description	CI_STATE_L.DESCR	
COUNTRY_DESCR	Country Description	CI_COUNTRY_L.DESCR	
CROSS_STREET	Cross Street	M1_LOCATION.CROSS_ STREET	
SUBURB	Suburb	M1_LOCATION.SUBURB	
STATE_CD	State Code	M1_LOCATION.STATE	
COUNTRY_CD	Country Code	M1_LOCATION.COUNT RY	
GEO_CODE	Geographical Code		
User Defined Attributes			
UDF1_CD	City Code	M1_LOCATION.UPPER( CITY)	
UDF1_DESCR	City Description	M1_LOCATION.UPPER( CITY)	
UDF2_CD	County Code	M1_LOCATION.COUNT Y	
UDF2_DESCR	County Description	M1_LOCATION.COUNT Y	

Target Field	Description	Source Field	Transformation Logic
UDF3_CD	Postal Code	M1_LOCATION.POSTAL	
UDF3_DESCR	Postal Code	M1_LOCATION.POSTAL	
UDF4_CD	State Code	M1_LOCATION.STATE	
UDF4_DESCR	State Description	CI_STATE_L.DESCR	
UDF5_CD	Country Code	M1_LOCATION.COUNT RY	
UDF5_DESCR	Country Description	CI_COUNTRY_L.DESCR	
UDF6_CD	Geo Code Value		
UDF6_DESCR	Geo Code		
UDF7_CD	Premise Char 1 Code		
UDF7_DESCR	Premise Char 1		
UDF8_CD	Premise Char 2 Code		
UDF8_DESCR	Premise Char 2		
UDF9_CD	Premise Char 3 Code		
UDF9_DESCR	Premise Char 3		
UDF10_CD	Premise Char 4 Code		
UDF10_DESCR	Premise Char 4 Code		
UDF11_CD	User Defined Field 11 Code		
UDF11_DESCR	User Defined Field 11 Description		
UDF12_CD	User Defined Field 12 Code		
UDF12_DESCR	User Defined Field 12 Description		
UDF13_CD	User Defined Field 13 Code		
UDF13_DESCR	User Defined Field 13 Description		
UDF14_CD	User Defined Field 14 Code		
UDF14_DESCR	User Defined Field 14 Description		
UDF15_CD	User Defined Field 15 Code		
UDF15_DESCR	User Defined Field 15 Description		
UDF16_CD	User Defined Field 16 Code		
UDF16_DESCR	User Defined Field 16 Description		

Target Field	Description	Source Field	Transformation Logic
UDF1_NUM	User Defined Field 1 Number		
UDF2_NUM	User Defined Field 2 Number		
UDF3_NUM	User Defined Field 3 Number		
UDF4_NUM	User Defined Field 4 Number		
UDF5_NUM	User Defined Field 5 Number		
UDF6_NUM	User Defined Field 6 Number		
UDF7_NUM	User Defined Field 7 Number		
UDF8_NUM	User Defined Field 8 Number		
UDF9_NUM	User Defined Field 9 Number		
UDF10_NUM	User Defined Field 10 Number		
UDF1_DATE	User Defined Field 1 Date		
UDF2_DATE	User Defined Field 2 Date		
UDF3_DATE	User Defined Field 3 Date		
UDF4_DATE	User Defined Field 4 Date		
UDF5_DATE	User Defined Field 5 Date		
UDF6_DATE	User Defined Field 6 Date		
UDF7_DATE	User Defined Field 7 Date		
UDF8_DATE	User Defined Field 8 Date		
UDF9_DATE	User Defined Field 9 Date		
UDF10_DATE	User Defined Field 10 Date		
FLEXFIELD1	Flex Field 1		
FLEXFIELD2	Flex Field 2		
FLEXFIELD3	Flex Field 3		
FLEXFIELD4	Flex Field 4		
FLEXFIELD5	Flex Field 5		
FLEXFIELD6	Flex Field 6		
FLEXFIELD7	Flex Field 7		

Target Field	Description	Source Field	Transformation Logic
FLEXFIELD8	Flex Field 8		
FLEXFIELD9	Flex Field 9		
FLEXFIELD10	Flex Field 10		
Data Load Attributes			
EFF_END_DTTM	Effective End Date/Time		
EFF_START_DTTM	Effective Start Date/Time		
DATA_LOAD_DTTM	Data Load Date/Time		This field is populated with the load timestamp value.
DATA_SOURCE_IND	Data Source Indicator	CI_INSTALLATION.ENV _ID	This field is populated with the DSI value on the source product instance configuration. The table is populated as part of the initial setup and the DSI value is extracted from the environment ID of the source system.
JOB_NBR	Job Number		This field is populated with the ODI job execution session number.

# Source 3 - POU (M1\_POU)

Target Field	Description	Source Field	Transformation Logic
Surrogate Key			
ADDR_KEY	Address Dimension Surrogate Key		This field is populated from the SPL_ADDR_SEQ sequence.

Target Field	Description	Source Field	Transformation Logic
Natural Keys			
SRC_ADDR_ID	Premise ID	M1_POU.ADDRESS1	This natural key is the concatenation of all address attributes, in uppercase.
		M1_POU.ADDRESS2	
		M1_POU.ADDRESS3	
		M1_POU.ADDRESS4	
		M1_POU.CROSS_STREE T	
		M1_POU.SUBURB	
		M1_POU.CITY	
		M1_POU.COUNTY	
		M1_POU.STATE	
		M1_POU.POSTAL	
		M1_POU.COUNTRY	
Attributes			
ADDR_LINE1	Address Line 1	M1_POU.ADDRESS1	
ADDR_LINE2	Address Line 2	M1_POU.ADDRESS2	
ADDR_LINE3	Address Line 3	M1_POU.ADDRESS3	
ADDR_LINE4	Address Line 4	M1_POU.ADDRESS4	
ADDR_INFO	Address Information	M1_POU.ADDRESS1	This field is populated from
		M1_POU.CITY	the POU table based on the concatenation of the address,
		M1_POU.STATE	city, state, and postal code.
		M1_POU.POSTAL	
CITY	City	M1_POU.UPPER(CITY)	
COUNTY	County	M1_POU.COUNTY	
POSTAL	Postal Code	M1_POU.POSTAL	
STATE_DESCR	State Description	CI_STATE_L.DESCR	
COUNTRY_DESCR	Country Description	CI_COUNTRY_L.DESCR	
CROSS_STREET	Cross Street	M1_POU.CROSS_STREE T	
SUBURB	Suburb	M1_POU.SUBURB	

Target Field	Description	Source Field	Transformation Logic
STATE_CD	State Code	M1_POU.STATE	
COUNTRY_CD	Country Code	M1_POU.COUNTRY	
GEO_CODE	Geographical Code		
User Defined Attributes			
UDF1_CD	City Code	M1_POU.UPPER(CITY)	
UDF1_DESCR	City Description	M1_POU.UPPER(CITY)	
UDF2_CD	County Code	M1_POU.COUNTY	
UDF2_DESCR	County Description	M1_POU.COUNTY	
UDF3_CD	Postal Code	M1_POU.POSTAL	
UDF3_DESCR	Postal Code Description	M1_POU.POSTAL	
UDF4_CD	State Code	M1_POU.STATE	
UDF4_DESCR	State Description	CI_STATE_L.DESCR	
UDF5_CD	Country Code	M1_POU.COUNTRY	
UDF5_DESCR	Country Description	CI_COUNTRY_L.DESCR	
UDF6_CD	Geo Code Value		
UDF6_DESCR	Geo Code		
UDF7_CD	Premise Char 1 Code		
UDF7_DESCR	Premise Char 1		
UDF8_CD	Premise Char 2 Code		
UDF8_DESCR	Premise Char 2		
UDF9_CD	Premise Char 3 Code		
UDF9_DESCR	Premise Char 3		
UDF10_CD	Premise Char 4 Code		
UDF10_DESCR	Premise Char 4 Code		
UDF11_CD	User Defined Field 11 Code		
UDF11_DESCR	User Defined Field 11 Description		
UDF12_CD	User Defined Field 12 Code		
UDF12_DESCR	User Defined Field 12 Description		
UDF13_CD	User Defined Field 13 Code		
UDF13_DESCR	User Defined Field 13 Description		
UDF14_CD	User Defined Field 14 Code		

Target Field	Description	Source Field	Transformation Logic
UDF14_DESCR	User Defined Field 14 Description		
UDF15_CD	User Defined Field 15 Code		
UDF15_DESCR	User Defined Field 15 Description		
UDF16_CD	User Defined Field 16 Code		
UDF16_DESCR	User Defined Field 16 Description		
UDF1_NUM	User Defined Field 1 Number		
UDF2_NUM	User Defined Field 2 Number		
UDF3_NUM	User Defined Field 3 Number		
UDF4_NUM	User Defined Field 4 Number		
UDF5_NUM	User Defined Field 5 Number		
UDF6_NUM	User Defined Field 6 Number		
UDF7_NUM	User Defined Field 7 Number		
UDF8_NUM	User Defined Field 8 Number		
UDF9_NUM	User Defined Field 9 Number		
UDF10_NUM	User Defined Field 10 Number		
UDF1_DATE	User Defined Field 1 Date		
UDF2_DATE	User Defined Field 2 Date		
UDF3_DATE	User Defined Field 3 Date		
UDF4_DATE	User Defined Field 4 Date		
UDF5_DATE	User Defined Field 5 Date		
UDF6_DATE	User Defined Field 6 Date		
UDF7_DATE	User Defined Field 7 Date		
UDF8_DATE	User Defined Field 8 Date		
UDF9_DATE	User Defined Field 9 Date		
UDF10_DATE	User Defined Field 10 Date		

Target Field	Description	Source Field	Transformation Logic
FLEXFIELD1	Flex Field 1		
FLEXFIELD2	Flex Field 2		
FLEXFIELD3	Flex Field 3		
FLEXFIELD4	Flex Field 4		
FLEXFIELD5	Flex Field 5		
FLEXFIELD6	Flex Field 6		
FLEXFIELD7	Flex Field 7		
FLEXFIELD8	Flex Field 8		
FLEXFIELD9	Flex Field 9		
FLEXFIELD10	Flex Field 10		
Data Load Attributes			
EFF_END_DTTM	Effective End Date/Time		
EFF_START_DTTM	Effective Start Date/Time		
DATA_LOAD_DTTM	Data Load Date/Time		This field is populated with the load timestamp value.
DATA_SOURCE_IND	Data Source Indicator	CI_INSTALLATION.ENV _ID	This field is populated with the DSI value on the source product instance configuration. The table is populated as part of the initial setup and the DSI value is extracted from the environment ID of the source system.
JOB_NBR	Job Number		This field is populated with the ODI job execution session number.

### Source 4 - Resource (M1\_RESRC)

Target Field	Description	Source Field	Transformation Logic
Surrogate Key			
ADDR_KEY	Address Dimension Surrogate Key		This field is populated from the SPL_ADDR_SEQ sequence.
Natural Keys			
SRC_ADDR_ID	Premise ID	M1_RESRC.BO_DATA_ AREA	This natural key is the concatenation of all address attributes, in uppercase.

Target Field	Description	Source Field	Transformation Logic
Attributes			
ADDR_LINE1	Address Line 1	M1_RESRC.BO_DATA_ AREA	
ADDR_LINE2	Address Line 2	M1_RESRC.BO_DATA_ AREA	
ADDR_LINE3	Address Line 3	M1_RESRC.BO_DATA_ AREA	
ADDR_LINE4	Address Line 4	M1_RESRC.BO_DATA_ AREA	
ADDR_INFO	Address Information	M1_RESRC.BO_DATA_ AREA	This field is populated from the Task Address table based on the concatenation of the address, city, state, and postal code.
CITY	City	M1_RESRC.BO_DATA_ AREA	
COUNTY	County	M1_RESRC.BO_DATA_ AREA	
POSTAL	Postal Code	M1_RESRC.BO_DATA_ AREA	
STATE_DESCR	State Description	CI_STATE_L.DESCR	
COUNTRY_DESCR	Country Description	CI_COUNTRY_L.DESCR	
CROSS_STREET	Cross Street	M1_RESRC.BO_DATA_ AREA	
SUBURB	Suburb	M1_RESRC.BO_DATA_ AREA	
STATE_CD	State Code	M1_RESRC.BO_DATA_ AREA	
COUNTRY_CD	Country Code	M1_RESRC.BO_DATA_ AREA	
GEO_CODE	Geographical Code		
User Defined Attributes			
UDF1_CD	City Code	M1_RESRC.BO_DATA_ AREA	
UDF1_DESCR	City Description	M1_RESRC.BO_DATA_ AREA	
UDF2_CD	County Code	M1_RESRC.BO_DATA_ AREA	
UDF2_DESCR	County Description	M1_RESRC.BO_DATA_ AREA	

Target Field	Description	Source Field	Transformation Logic
UDF3_CD	Postal Code	M1_RESRC.BO_DATA_ AREA	
UDF3_DESCR	Postal Code Description	M1_RESRC.BO_DATA_ AREA	
UDF4_CD	State Code	M1_RESRC.BO_DATA_ AREA	
UDF4_DESCR	State Description	CI_COUNTRY_L.DESCR	
UDF5_CD	Country Code	M1_POU.COUNTRY	
UDF5_DESCR	Country Description	CI_COUNTRY_L.DESCR	
UDF6_CD	Geo Code Value		
UDF6_DESCR	Geo Code Description		
UDF7_CD	Premise Char 1 Code		
UDF7_DESCR	Premise Char 1 Description		
UDF8_CD	Premise Char 2 Code		
UDF8_DESCR	Premise Char 2 Description		
UDF9_CD	Premise Char 3 Code		
UDF9_DESCR	Premise Char 3 Description		
UDF10_CD	Premise Char 4 Code		
UDF10_DESCR	Premise Char 4 Description		
UDF11_CD	User Defined Field 11 Code		
UDF11_DESCR	User Defined Field 11 Description		
UDF12_CD	User Defined Field 12 Code		
UDF12_DESCR	User Defined Field 12 Description		
UDF13_CD	User Defined Field 13 Code		
UDF13_DESCR	User Defined Field 13 Description		
UDF14_CD	User Defined Field 14 Code		
UDF14_DESCR	User Defined Field 14 Description		
UDF15_CD	User Defined Field 15 Code		
UDF15_DESCR	User Defined Field 15 Description		
UDF16_CD	User Defined Field 16 Code		

Target Field	Description	Source Field	Transformation Logic
UDF16_DESCR	User Defined Field 16 Description		
UDF1_NUM	User Defined Field 1 Number		
UDF2_NUM	User Defined Field 2 Number		
UDF3_NUM	User Defined Field 3 Number		
UDF4_NUM	User Defined Field 4 Number		
UDF5_NUM	User Defined Field 5 Number		
UDF6_NUM	User Defined Field 6 Number		
UDF7_NUM	User Defined Field 7 Number		
UDF8_NUM	User Defined Field 8 Number		
UDF9_NUM	User Defined Field 9 Number		
UDF10_NUM	User Defined Field 10 Number		
UDF1_DATE	User Defined Field 1 Date		
UDF2_DATE	User Defined Field 2 Date		
UDF3_DATE	User Defined Field 3 Date		
UDF4_DATE	User Defined Field 4 Date		
UDF5_DATE	User Defined Field 5 Date		
UDF6_DATE	User Defined Field 6 Date		
UDF7_DATE	User Defined Field 7 Date		
UDF8_DATE	User Defined Field 8 Date		
UDF9_DATE	User Defined Field 9 Date		
UDF10_DATE	User Defined Field 10 Date		
FLEXFIELD1	Flex Field 1		
FLEXFIELD2	Flex Field 2		
FLEXFIELD3	Flex Field 3		
FLEXFIELD4	Flex Field 4		
FLEXFIELD5	Flex Field 5		

Target Field	Description	Source Field	Transformation Logic
FLEXFIELD6	Flex Field 6		
FLEXFIELD7	Flex Field 7		
FLEXFIELD8	Flex Field 8		
FLEXFIELD9	Flex Field 9		
FLEXFIELD10	Flex Field 10		
Data Load Attributes			
EFF_END_DTTM	Effective End Date/Time		
EFF_START_DTTM	Effective Start Date/Time		
DATA_LOAD_DTTM	Data Load Date/Time		This field is populated with the load timestamp value.
DATA_SOURCE_IND	Data Source Indicator	CI_INSTALLATION.ENV _ID	This field is populated with the DSI value on the source product instance configuration. The table is populated as part of the initial setup and the DSI value is extracted from the environment ID of the source system.
JOB_NBR	Job Number		This field is populated with the ODI job execution session number.

#### Crew

The Crew dimension includes the details of all crews defined in the source system up to three levels of crew hierarchy.

This dimension is also populated by Oracle Utilities Network Management System.

# **Properties**

Property	Value
Target Table	CD_CREW
Table Type	Dimension
SCD Type	Type 2
Source System Driver Table	M1_RESRC M1_RESRC_TYPE M1_HIERARCHY
Stage Table	STG_CD_CREW
ODI Package	B1_PKG_CD_CREW
ETL View	B1_D_CREW_VW

Target Field	Description	Source Field	Transformation Logic
Surrogate Key			
CREW_KEY	Crew Dimension Surrogate Key		This field is populated from the SPL_CREW_SEQ sequence.
Natural Keys			
SRC_CREW_ID	Crew ID	M1_RESRC.RESRC_ID	
Attributes			
CREW_DESCR	Crew Description	M1_RESRC_ID.RESRC_I D_VAL	
CREW_TYPE_DESCR	Crew Type Description	M1_RESRC_TYPE_L.DES CR	
CREW_CD	Crew Code		Note: This field is populated only for the Oracle Utilities Network Management System source product.
CREW_TYPE_CD	Crew Type Code	M1_RESRC.RESRC_TYPE _CD	

Target Field	Description	Source Field	Transformation Logic
ORG_UNIT1_CD	Crew Hierarchy-1 Code	M1_HIER_UPSTREAM.M 1_PARENT_HIER_CD	This field is populated from the Hierarchy Upstream table based on the hierarchy and hierarchy level.
			Note: The hierarchy is based on the reporting hierarchy stored on the crew's characteristic (where characteristic type is Crew Hierarchy 'M1CRHIER') and for which the hierarchy level is Level 1 ('M101').
ORG_UNIT2_CD	Crew Hierarchy-2 Code	M1_HIER_UPSTREAM.M 1_PARENT_HIER_CD	This field is populated from the Hierarchy Upstream table based on the hierarchy and hierarchy level.
			Note: The hierarchy is based on the reporting hierarchy stored on the crew's characteristic (where characteristic type is Crew Hierarchy 'M1CRHIER') and for which the hierarchy level is Level 1 ('M102').
ORG_UNIT3_CD	Crew Hierarchy-3 Code	M1_HIER_UPSTREAM.M 1_PARENT_HIER_CD	This field is populated from the Hierarchy Upstream table based on the hierarchy and hierarchy level.
			Note: The hierarchy is based on the reporting hierarchy stored on the crew's characteristic (where characteristic type is Crew Hierarchy 'M1CRHIER') and for which the hierarchy level is Level 1 ('M103').
ORG_UNIT1_DESCR	Crew Hierarchy-1 Description	M1_HIERARCHY_L.DES CR	This field is populated from the hierarchy description based on the parent hierarchy code and language configured.
			Note: To retrieve the parent hierarchy code, see the transformation logic of the ORG_UNIT1_CD column.

Target Field	Description	Source Field	Transformation Logic
ORG_UNIT2_DESCR	Crew Hierarchy-2 Description	M1_HIERARCHY_L.DES CR	This field is populated from the hierarchy description based on the parent hierarchy code and language configured.
			<b>Note</b> : To retrieve the parent hierarchy code, see the transformation logic of the ORG_UNIT2_CD column.
ORG_UNIT3_DESCR	Crew Hierarchy-3 Description	M1_HIERARCHY_L.DES CR	This field is populated from the hierarchy description based on the parent hierarchy code and language configured.
			<b>Note</b> : To retrieve the parent hierarchy code, see the transformation logic of the ORG_UNIT3_CD column.
User Defined Attributes			
UDF1_CD	User Defined Field 1 Code		
UDF1_DESCR	User Defined Field 1 Description		
UDF2_CD	User Defined Field 2 Code		
UDF2_DESCR	User Defined Field 2 Description		
UDF3_CD	User Defined Field 3 Code		
UDF3_DESCR	User Defined Field 3 Description		
UDF4_CD	User Defined Field 4 Code		
UDF4_DESCR	User Defined Field 4 Description		
UDF5_CD	User Defined Field 5 Code		
UDF5_DESCR	User Defined Field 5 Description		
UDF6_CD	User Defined Field 6 Code		
UDF6_DESCR	User Defined Field 6 Description		
UDF7_CD	User Defined Field 7Code		
UDF7_DESCR	User Defined Field 7 Description		
UDF8_CD	User Defined Field 8 Code		

Target Field	Description	Source Field	Transformation Logic
UDF8_DESCR	User Defined Field 8 Description		
UDF9_CD	User Defined Field 9 Code		
UDF9_DESCR	User Defined Field 9 Description		
UDF10_CD	User Defined Field 10 Code		
UDF10_DESCR	User Defined Field 10 Description		
Data Load Attributes			
EFF_END_DTTM	Effective End Date/Time		
EFF_START_DTTM	Effective Start Date/Time		
DATA_LOAD_DTTM	Data Load Date/Time		This field is populated with the load timestamp value.
DATA_SOURCE_IND	Data Source Indicator	CI_INSTALLATION.ENV _ID	This field is populated with the DSI value on the source product instance configuration. The table is populated as part of the initial setup and the DSI value is extracted from the environment ID of the source system.
JOB_NBR	Job Number		This field is populated with the ODI job execution session number.

#### Contact

Though Contact dimension is referenced in the Oracle Utilities Mobile Workforce Management facts, it is populated only by the Oracle Utilities Meter Data Management source product. The ETL processes of the Oracle Utilities Mobile Workforce Management facts map this dimension based on the integration between Oracle Utilities Mobile Workforce Management and Oracle Utilities Meter Data Management.

Since this dimension is not populated by Oracle Utilities Mobile Workforce Management, the source mapping details are not provided in the document. See the *Oracle Utilities Extractors and Schema for Oracle Utilities Meter Data Management Data Mapping Guide* for the mapping details.

#### **Device**

Though Device dimension is referenced in the Oracle Utilities Mobile Workforce Management facts, it is populated only by the Oracle Utilities Meter Data Management source product. The ETL processes of the Oracle Utilities Mobile Workforce Management facts map this dimension based on the integration between Oracle Utilities Mobile Workforce Management and Oracle Utilities Meter Data Management.

Since this dimension is not populated by Oracle Utilities Mobile Workforce Management, the source mapping details are not provided in the document. See the *Oracle Utilities Extractors and Schema for Oracle Utilities Meter Data Management Data Mapping Guide* for the mapping details.

#### Person

Though Person dimension is referenced in the Oracle Utilities Meter Data Management facts, it is populated only by the Oracle Utilities Customer Care and Billing source product. The ETL processes of the Oracle Utilities Meter Data Management facts map this dimension based on the integration between Oracle Utilities Meter Data Management and Oracle Utilities Customer Care and Billing.

Since this dimension is not populated by Oracle Utilities Meter Data Management, the source mapping details are not provided in the document. See the *Oracle Utilities Extractors* and Schema for Oracle Utilities Customer Care and Billing Data Mapping Guide for the mapping details.

#### **Premise**

Though Premise dimension is referenced in the Oracle Utilities Meter Data Management facts, it is populated only by the Oracle Utilities Customer Care and Billing source product. The ETL processes of the Oracle Utilities Meter Data Management facts map this dimension based on the integration between Oracle Utilities Meter Data Management and Oracle Utilities Customer Care and Billing.

Since this dimension is not populated by Oracle Utilities Meter Data Management, the source mapping details are not provided in the document. See the *Oracle Utilities Extractors* and Schema for Oracle Utilities Customer Care and Billing Data Mapping Guide for the mapping details.

## **Service Agreement**

Though Service Agreement dimension is referenced in the Oracle Utilities Meter Data Management facts, it is populated only by the Oracle Utilities Customer Care and Billing source product. The ETL processes of the Oracle Utilities Meter Data Management facts map this dimension based on the integration between Oracle Utilities Meter Data Management and Oracle Utilities Customer Care and Billing.

Since this dimension is not populated by Oracle Utilities Meter Data Management, the source mapping details are not provided in the document. See the *Oracle Utilities Extractors* and Schema for Oracle Utilities Customer Care and Billing Data Mapping Guide for the mapping details.

#### **Service Point**

Though Service Point dimension is referenced in the Oracle Utilities Mobile Workforce Management facts, it is populated only by the Oracle Utilities Meter Data Management source product. The ETL processes of the Oracle Utilities Mobile Workforce

Management facts map this dimension based on the integration between Oracle Utilities Mobile Workforce Management and Oracle Utilities Meter Data Management.

Since this dimension is not populated by Oracle Utilities Mobile Workforce Management, the source mapping details are not provided in the document. See the *Oracle Utilities Extractors and Schema for Oracle Utilities Meter Data Management Data Mapping Guide* for the mapping details.

### **Usage Subscription**

Though Usage Subscription dimension is referenced in the Oracle Utilities Mobile Workforce Management facts, it is populated only by the Oracle Utilities Meter Data Management source product. The ETL processes of the Oracle Utilities Mobile Workforce Management facts map this dimension based on the integration between Oracle Utilities Mobile Workforce Management and Oracle Utilities Meter Data Management.


Since this dimension is not populated by Oracle Utilities Mobile Workforce Management, the source mapping details are not provided in the document. See the *Oracle Utilities Extractors and Schema for Oracle Utilities Meter Data Management Data Mapping Guide* for the mapping details.

# **Facts**

### **Completed Shift**

The Completed Shift fact holds the details of all completed shifts from the Oracle Utilities Mobile Workforce Management system that show the number of crews late to logon and by how much they deviated from the planned time, the number of crews early to logoff and by how much they deviated from the planned time, how much time the crew work overtime, and what are the deviations in estimated travel mileage versus actual mileage. This fact is populated based on completed, real shifts.

#### **Entity Relationship Diagram**



# **Properties**

Property	Value
Target Table Name	CF_CMP_SHIFT
Table Type	Fact
Fact Type	Accumulation
Source System Driver Table	M1_CREW_SHFT M1_RESRC M1_TASK M1_LOCATION
Stage Table Name	STG_CF_CMP_SHIFT
ODI Package Name	B1_PKG_CF_CMP_SHIFT
ETL View Name	B1_F_CMP_SHIFT_VW
Materialized View Name	B1_CMP_SHIFT_MON_MV1

### **Fields**

Description	Source Field	Transformation Logic
Completed Shift Surrogate Key		This field is populated from the OUBI_CMP_SHIFT_SEQ sequence.
Shift ID	M1_CREW_SHFT.CREW_ SHFT_ID	
Planned Duration (Seconds)	M1_CREW_SHFT.(PLAN_ START_DTTM - M1_CREW_SHFT.PLAN_ END_DTTM)	This field is populated with the planned duration of the shift. It is the difference between the planned start date time and end date time (in seconds).
Actual Duration (Seconds)	M1_CREW_SHFT. BUS_STATUS_DTTM - M1_CREW_SHFT_LOG. LOG_DTTM	This field is populated with the actual duration of the shift. It is populated with the difference (in seconds) between the actual start date time and actual completion date time.  Depending on the crew shift, the regular logs or the mobile
	Completed Shift Surrogate Key  Shift ID  Planned Duration (Seconds)	Completed Shift Surrogate Key  Shift ID  M1_CREW_SHFT.CREW_ SHFT_ID  Planned Duration (Seconds)  M1_CREW_SHFT.(PLAN_ START_DTTM - M1_CREW_SHFT.PLAN_ END_DTTM)  Actual Duration (Seconds)  M1_CREW_SHFT. BUS_STATUS_DTTM - M1_CREW_SHFT_LOG.

Target Field	Description	Source Field	Transformation Logic
OVERTIME_DUR	Overtime Duration (Seconds)	M1_CREW_SHFT.ACTUA L_DUR	This field is populated if the shift went overtime. It is calculated from the difference
		M1_CREW_SHFT.PLANN ED_DUR	between the actual duration and planned duration (in seconds).
			If the difference is greater than 0, overtime duration is populated.
EST_DISTANCE	Estimated Distance	M1_TASK.BO_DATA_AR EA	This field is the total of all estimated mileage of all tasks performed by the crew on the shift.
EST_TOT_MILEAGE	Estimated Total Mileage for Vehicles	M1_TASK.RESRC_ID	This field is the total of estimated mileage of all tasks
		M1_RESRC.BO_DATA_A REA	performed by the crew taking into consideration the resources allocated to the shift. It is populated with the sum of estimated travel distance for all tasks of the shift multiplied by the number of vehicles allocated to the shift.
ACT_TOT_MILEAGE	Actual Total Mileage for Vehicles	M1_CREW_SHFT_RESRC .BO_DATA_AREA	This field is populated by the actual total mileage of all vehicles allocated to the shift. It is populated based on the odometer readings at the start and end of the shift.
VEHICLE_CNT	Number of Vehicles	M1_RESRC.RESRC_ID	This field is populated with the total number of vehicles allocated to the shift. It is retrieved from resources where resource class is Vehicle ('M1VH').
FACT_CNT	Count		This field is populated with the standard value of '1'.
Degenerate Dimensions			
SHIFT_PLANNED_ START_DTTM	Shift Planned Start Date/ Time	M1_CREW_SHFT.PLAN_ START_DTTM	This field is populated with the plan start date time associated with the crew shift.
Foreign Keys			
CREW_SHIFT_KEY	Shift Dimension Surrogate Key	M1_CREW_SHFT.CREW_ SHFT_ID	This field is populated from the Crew Shift dimension based on the crew shift ID associated with the crew.

Target Field	Description	Source Field	Transformation Logic
CREW_KEY	Crew Dimension Surrogate Key	M1_CREW_SHFT.RESRC _ID	This field is populated from the Crew dimension based on the resource ID associated with the crew shift.
LATE_LOGON_TM_KEY	Late Logon Time Dimension Surrogate Key	M1_CREW_SHFT_LOG.L OG_DTTM - M1_CREW_SHFT.PLAN_ START_DTTM	This field is populated based on the late logon time calculated as the difference (in minutes) between the shift's actual start date/time and planned start date/time.  Depending on the crew shift, the regular logs or the mobile logs would be used.
EARLY_LOGOFF_TM_ KEY	Early Logoff Time Dimension Surrogate Key	M1_CREW_SHFT.PLAN_ END_DTTM - M1_CREW_SHFT.B US_STATUS_DTTM	This field is populated baed on the early logoff time calculated as the difference (in minutes) between the shift's actual end date/ time and planned end date/ time.
TRAVEL_DIST_DEV_ KEY	Travel Distance Deviation Dimension Surrogate Key		This field is calculated based on the percentage of deviation between actual total mileage and estimated total mileage calculated earlier in the fact.

Target Field	Description	Source Field	Transformation Logic
LOGON_ADDR_KEY	Logon Address Dimension Surrogate Key	M1_LOCATION/ M1_RESRC.ADDRESS1	This field is populated based on the logon location entered on the shift.
		M1_LOCATION/ M1_RESRC.ADDRESS2	If there is no logon location specified, but the logon
		M1_LOCATION/ M1_RESRC.ADDRESS3	location type is Home, the field is populated based on the home address of the first
		M1_LOCATION/ M1_RESRC.ADDRESS4	mobile worker allocated to the shift.
		M1_LOCATION/ M1_RESRC.CROSS_STRT	
		M1_LOCATION/ M1_RESRC.SUBURB	
		M1_LOCATION/ M1_RESRC.CITY	
		M1_LOCATION/ M1_RESRC.COUNTY	
		M1_LOCATION/ M1_RESRC.STATE	
		M1_LOCATION/ M1_RESRC.POSTAL	
		M1_LOCATION/ M1_RESRC.COUNTRY	
		M1_LOCATION/ M1_RESRC.BO_DATA_A REA	

Target Field	Description	Source Field	Transformation Logic
LOGOFF_ADDR_KEY	Logoff Address Dimension Surrogate Key	M1_LOCATION/ M1_RESRC.ADDRESS1	This field is populated based on the logoff location entered on the shift.
		M1_LOCATION/ M1_RESRC.ADDRESS2	If there is no logoff location
		M1_LOCATION/ M1_RESRC.ADDRESS3	specified, but the logoff location type is Home, the field is populated based on the home address of the first
		M1_LOCATION/ M1_RESRC.ADDRESS4	mobile worker allocated to the shift.
		M1_LOCATION/ M1_RESRC.CROSS_STRT	
		M1_LOCATION/ M1_RESRC.SUBURB	
		M1_LOCATION/ M1_RESRC.CITY	
		M1_LOCATION/ M1_RESRC.COUNTY	
		M1_LOCATION/ M1_RESRC.STATE	
		M1_LOCATION/ M1_RESRC.POSTAL	
		M1_LOCATION/ M1_RESRC.COUNTRY	
		M1_LOCATION/ M1_RESRC.BO_DATA_A REA	
SHIFT_PLANNED_ START_DATE_KEY	Shift Planned Start Date Key	M1_CREW_SHFT.PLAN_ START_DTTM	This field is populated from the Crew Shift table based on the planned start date associated with the crew shift.
SHIFT_PLANNED_ START_TIME_KEY	Shift Planned Start Time Key	M1_CREW_SHFT.PLAN_ START_DTTM	This field is populated from the Crew Shift table based on the planned start time associated with the crew shift.
CMP_SHIFT_UDD1_KEY	Completed Shift User Defined Dimension 1 Key		
CMP_SHIFT_UDD2_KEY	Completed Shift User Defined Dimension 2 Key		
User Defined Attributes			
UDM1	User Defined Measure 1		


Target Field	Description	Source Field	Transformation Logic
UDM2	User Defined Measure 2		
UDM3	User Defined Measure 3		
UDM4	User Defined Measure 4		
UDM5	User Defined Measure 5		
UDM6	User Defined Measure 6		
UDM7	User Defined Measure 7		
UDM8	User Defined Measure 8		
UDM9	User Defined Measure 9		
UDM10	User Defined Measure 10		
UDDGEN1	User Defined Degenerate Dimension 1		
UDDGEN2	User Defined Degenerate Dimension 2		
UDDGEN3	User Defined Degenerate Dimension 3		
UDDGEN4	User Defined Degenerate Dimension 4		
UDDGEN5	User Defined Degenerate Dimension 5		
UDDGENL1	User Defined Long Degenerate Dimension 1		
UDDGENL2	User Defined Long Degenerate Dimension 2		
UDDGENL3	User Defined Long Degenerate Dimension 3		
UDDGENL4	User Defined Long Degenerate Dimension 4		
UDDGENL5	User Defined Long Degenerate Dimension 5		
UDDFK1_KEY	User Defined Dimension Foreign Key 1		
UDDFK2_KEY	User Defined Dimension Foreign Key 2		
UDDFK3_KEY	User Defined Dimension Foreign Key 3		
UDDFK4_KEY	User Defined Dimension Foreign Key 4		
UDDFK5_KEY	User Defined Dimension Foreign Key 5		

Target Field	Description	Source Field	Transformation Logic
Data Load Attributes			
DATA_SOURCE_IND	Data Source Indicator	CI_INSTALLATION.ENV _ID	This field is populated with the DSI value on the source product instance configuration. This table is populated as part of the initial setup and the DSI value is extracted from the environment ID of the source system.
JOB_NBR	Job Number		This field is populated with the ODI job execution session number.

### **Crew Task**

The Crew Tasks fact has measures that show how much time the crews spend on productive versus non-productive tasks; how much time crews spend working on each task, as well as time spent in and out of services; how many times a crew makes or misses appointments, and if missed, by how much; and how many times crews arrive at an activity, but fail to complete it.

#### **Entity Relationship Diagram**



# **Properties**

Property	Value
Target Table Name	CF_CREW_TASK
Table Type	Fact
Fact Type	Accumulation
Source System Driver Table	M1_CREW_SHFT M1_TASK M1_LOCATION M1_POU
Stage Table Name	STG_CF_CREW_TASK
ODI Package Name	B1_PKG_CF_CREW_TASK
ETL View Name	B1_F_CREW_TASK_VW
Materialized View Name	B1_CREW_TASKS_MON_MV1

### **Fields**

Target Field	Description	Source Field	Transformation Logic
Surrogate Key			
CREW_TASK_KEY	Crew Task Surrogate Key		This field is populated from the OUBI_CREW_TASK_SEQ sequence.
Natural Keys			
SRC_SHIFT_ID	Shift ID	M1_CREW_SHFT.CREW_ SHFT_ID	
SRC_TASK_ID	Activity ID	M1_TASK.TASK_ID	
SRC_SHIFT_LOG_SEQ	Shift Log Sequence	M1_CREW_SHFT_LOG.S EQNO	Depending on the crew shift, the regular logs or mobile logs are used.
SRC_TASK_LOG_SEQ	Task Log Sequence	M1_TASK_LOG.SEQNO	Depending on the crew shift, the regular logs or mobile logs are used.
Measures			
PREV_STATE_DUR	Time in Previous State		This field is populated with the time spent (in seconds) in the previous state based on the log date/times.
EST_TRAVEL_DUR	Estimated	M1_TASK.BO_DATA_AR EA	This field is populated with the estimated travel duration from CLOB in the source Task table.

Target Field	Description	Source Field	Transformation Logic
FACT_CNT	Count		This field is populated with the standard value of '1'.
Degenerate Dimensions			
APPOINTMENT_IND	Appointment Indicator	M1_TASK.APPOINTME NT_FLG	This field is populated based on the appointment flag from the Task table. If the appointment flag is 'Y', the appointment indicator is populated with '1'. Else, with '0'.
EMERGENCY_IND	Emergency Indicator	M1_TASK.QUEUE_FLG	This field is populated based on the queue flag from the source Task table. If the queue flag is 'M1ER', the emergency indicator is populated with '1'. Else, with '0'.
FROM_DTTM	From Date/Time	M1_CREW_SHFT_LOG.L OG_DTTM M1_TASK_LOG.LOG_D TTM	
TO_DTTM	To Date/Time	M1_CREW_SHFT_LOG.L OG_DTTM	
		M1_TASK_LOG.LOG_D TTM	
Foreign Keys			
CREW_TM_USG_KEY	Crew Time Usage Dimension Surrogate Key		This field is populated based on the task class and crew shift status or task status.
FROM_SHIFT_BO_ STATUS_KEY	From Shift BO Status Dimension Surrogate Key	M1_CREW_SHFT.BUS_O BJ_CD M1_CREW_SHFT_LOG.B O_STATUS_CD	This field is populated based on shift status from the log entries.
		M1_CREW_SHFT_LOG.B O_STATUS_REASON_C D	

Target Field	Description	Source Field	Transformation Logic
TO_SHIFT_BO_STATUS_ KEY	To Shift BO Status Dimension Surrogate Key	M1_CREW_SHFT.BUS_O BJ_CD	This field is populated based on shift status from the log entries.
		M1_CREW_SHFT_LOG.B O_STATUS_CD	citales.
		M1_CREW_SHFT_LOG.B O_STATUS_REASON_C D	
CREW_SHIFT_KEY	Shift Dimension Surrogate Key	M1_CREW_SHFT.CREW_ SHFT_ID	This field is populated from the Crew Shift dimension based on the crew shift ID.
CREW_KEY	Crew Dimension Surrogate Key	M1_CREW_SHFT.RESRC _ID	This field is populated from the Crew dimension based on the resource ID associated with the crew shift.
TRAVEL_DUR_DEV_ KEY	Travel Duration Deviation Dimension Surrogate Key		This field is calculated based on the percentage of deviation between actual travel duration based on the log date/times and the estimated travel duration.
APPT_TM_KEY	Appointment Time Dimension Surrogate Key		This field is populated based on the difference between task time window start and end date/time associated with the task ID.
APPT_TM_OF_DAY_KEY	Appointment Time of Day Dimension Surrogate Key		This field is populated based on the task time window start date/time associated with the task ID.
FROM_TASK_BO_ STATUS_KEY	From Task BO Status Dimension Surrogate Key	M1_TASK.BUS_OBJ_CD	This field is populated based on the task status from log
31M103_KL1	Dimension Surrogate Key	M1_TASK_LOG.BO_STA TUS_CD	entries.
		M1_TASK_LOG.BO_STA TUS_REASON_CD	
TO_TASK_BO_STATUS_ KEY	To Task BO Status Dimension Surrogate Key	M1_TASK.BUS_OBJ_CD	This field is populated based on the task status from log
KL1	Dimension Surrogate Key	M1_TASK_LOG.BO_STA TUS_CD	entries.
		M1_TASK_LOG.BO_STA TUS_REASON_CD	
TASK_TYPE_KEY	Task Type Dimension Surrogate Key	M1_TASK.TASK_TYPE_ CD	This field is populated based on the task type code associated with the task ID.

Target Field	Description	Source Field	Transformation Logic
SERVICE_AREA_KEY	Service Area Dimension Surrogate Key	M1_TASK.SVC_AREA_C D	This field is populated based on the task type code associated with the task ID.
ADDR_KEY	Address Dimension Surrogate Key		This field is populated based on the address constituents associated with the task.
			Based on the task class, the address constituents are fetched either from the task, location, depot, or period of unavailability entity.
FROM_DATE_KEY	From Date Dimension Surrogate Key	M1_CREW_SHFT_LOG.L OG_DTTM	This field is populated based on the log date from shift log or task log.
		M1_TASK_LOG.LOG_D TTM	
TO_DATE_KEY	To Date Dimension Surrogate Key	M1_CREW_SHFT_LOG.L OG_DTTM	This field is populated based on the log date from shift log or task log.
		M1_TASK_LOG.LOG_D TTM	32 mm 13g
FROM_TIME_KEY	From Time Dimension Surrogate Key	M1_CREW_SHFT_LOG.L OG_DTTM	This field is populated based on the log date from shift log or task log.
		M1_TASK_LOG.LOG_D TTM	S
TO_TIME_KEY	To Time Dimension Surrogate Key	M1_CREW_SHFT_LOG.L OG_DTTM	This field is populated based on the log date from shift log or task log.
		M1_TASK_LOG.LOG_D TTM	
MTR_DEVICE_KEY	Device Dimension Surrogate Key	M1_TASK.BO_DATA_AR EA	This field is populated based on the external identifier value for the meter device stored on the task as part of MWM-MDM integration.
SP_KEY	Service Point Dimension Surrogate Key	M1_TASK.BO_DATA_AR EA	This field is populated based on the service point ID stored on the task as part of MWM-MDM integration.
US_KEY	Usage Subscription Dimension Surrogate Key	M1_TASK.BO_DATA_AR EA	This field is populated based on the usage subscription ID stored on the task as part of MWM-MDM integration.


Target Field	Description	Source Field	Transformation Logic
CONTACT_KEY	Contact Dimension Surrogate Key	M1_TASK.BO_DATA_AR EA	This field is populated based on the contact ID stored on the task as part of MWM-MDM integration.
PER_KEY	Person Dimension Surrogate Key	M1_TASK.BO_DATA_AR EA	This field is populated based on the person ID stored on task as part of MWM-CCB integration.
ACCT_KEY	Account Dimension Surrogate Key	M1_TASK.BO_DATA_AR EA	This field is populated based on the account ID stored on task as part of MWM-CCB integration.
SA_KEY	Service Agreement Dimension Surrogate Key	M1_TASK.BO_DATA_AR EA	This field is populated based on the service agreement ID stored on task as part of MWM-CCB integration.
PREM_KEY	Premise Dimension Surrogate Key	M1_TASK.BO_DATA_AR EA	This field is populated based on the premise ID stored on task as part of MWM-CCB integration.
CREW_TASK_UDD1_ KEY	Crew Task User Defined Dimension 1 Key		
CREW_TASK_UDD2_ KEY	Crew Task User Defined Dimension 2 Key		
User Defined Attributes			
UDM1	User Defined Measure 1		
UDM2	User Defined Measure 2		
UDM3	User Defined Measure 3		
UDM4	User Defined Measure 4		
UDM5	User Defined Measure 5		
UDM6	User Defined Measure 6		
UDM7	User Defined Measure 7		
UDM8	User Defined Measure 8		
UDM9	User Defined Measure 9		
UDM10	User Defined Measure 10		
UDDGEN1	User Defined Degenerate Dimension 1		
UDDGEN2	User Defined Degenerate Dimension 2		

Target Field	Description	Source Field	Transformation Logic
UDDGEN3	User Defined Degenerate Dimension 3		
UDDGEN4	User Defined Degenerate Dimension 4		
UDDGEN5	User Defined Degenerate Dimension 5		
UDDGENL1	User Defined Long Degenerate Dimension 1		
UDDGENL2	User Defined Long Degenerate Dimension 2		
UDDGENL3	User Defined Long Degenerate Dimension 3		
UDDGENL4	User Defined Long Degenerate Dimension 4		
UDDGENL5	User Defined Long Degenerate Dimension 5		
UDDFK1_KEY	User Defined Dimension Foreign Key 1		
UDDFK2_KEY	User Defined Dimension Foreign Key 2		
UDDFK3_KEY	User Defined Dimension Foreign Key 3		
UDDFK4_KEY	User Defined Dimension Foreign Key 4		
UDDFK5_KEY	User Defined Dimension Foreign Key 5		
Data Load Attributes			
DATA_SOURCE_IND	Data Source Indicator	CI_INSTALLATION.ENV _ID	This field is populated with the DSI value on the source product instance configuration. This table is populated as part of the initial setup and the DSI value is extracted from the environment ID of the source system.
JOB_NBR	Job Number		This field is populated with the ODI job execution session number.

### **Field Activity**

The Field Activity fact holds the details of all activities (tasks) defined in the Oracle Utilities Extractors and Schema for Oracle Utilities Mobile Workforce Management system with measures around duration quantities, response times, and emergency indicator.

#### **Entity Relationship Diagram**



# **Properties**

Property	Value
Target Table Name	CF_FLD_ACTIVITY
Table Type	Fact
Fact Type	Accumulation
Source System Driver Table	M1_TASK M1_CREW_SHFT
Stage Table Name	STG_CF_FLD_ACTIVITY
ODI Package Name	B1_PKG_CF_FLD_ACTIVITY
ETL View Name	B1_F_FLD_ACTIVITY_VW
Materialized View Name	B1_FLD_ACTIVITY_MON_MV1 B1_FLD_ACTIVITY_MON_MV2 B1_FLD_ACTIVITY_MON_MV3

### **Fields**

Target Field	Description	Source Field	Transformation Logic
Surrogate Key			
FLD_ACTIVITY_KEY	Activity Surrogate Key		This field is populated from the OUBI_FLD_ACTIVITY_SE Q sequence.
Natural Keys			
SRC_TASK_ID	Activity ID	M1_TASK.TASK_ID	This field is populated from the source Task table based on the tasks for which the Task Flag is set to Activity ('M1AC') and Parent Task ID is set as blank.
Measures			
WORK_DUR	Work Duration (Minutes)	M1_TASK_TYPE.AVG_D UR	This field is populated with the average task duration from the Task Type table. If no value is found, '0' is populated.
EST_WORK_DUR	Estimated Work Duration	M1_TASK.ESTIMATED_ DURATION	This field is populated with the estimated task duration from the Task Type table. If no value is found, '0' is populated.

Target Field	Description	Source Field	Transformation Logic
ACT_WORK_DUR	Actual Work Duration	M1_TASK_LOG/ M1_TASK_MOB_LOG.L OG_DTTM	This field is populated with the total time spent 'onsite' (in seconds) by the crew. It is calculated based on the log entries.
WORK_ATTEMPT_CNT	Number of Work Attempts	M1_TASK_LOG/ M1_TASK_MOB_LOG.B O_STATUS_CD	This field is populated with the number of times crew attempted to do the work (based on the number of times the crew logged with an 'Onsite' status).
			If there are no log records, it is populated as '0'.
TRAVEL_ATTEMPT_CNT	Number of Travel Attempts	M1_TASK_LOG/ M1_TASK_MOB_LOG.B O_STATUS_CD	This field is populated with the number of times the crew traveled to the site to do the work (based on the number of times the crew logged with an 'Enroute' status).
			If there are no log records, it is populated as '0'.
DISPATCH_RESP_DUR	Creation To Dispatch	M1_TASK_LOG/ M1_TASK_MOB_LOG.L OG_DTTM	This field is populated based on the time (in seconds) between the creation of the
		M1_TASK.CRE_DTTM	activity until it was dispatched (based on the difference between the creation date/time and the log date/time of the log entry for 'Dispatched' status).
			If the activity has not been dispatched, it is populated as '0'.
ENROUTE_RESP_DUR	Dispatch to Enroute	M1_TASK_LOG/ M1_TASK_MOB_LOG.L OG_DTTM	This field is populated based on the time (in seconds) it took from dispatching the activity until the crew is en route to the site (based on the difference between the maximum log date time for the entry with 'Dispatched' status and the log entry with 'En Route' status.
			If there are no log records, it is populated as '0'.

Target Field	Description	Source Field	Transformation Logic
ARRIVAL_RESP_DUR	Enroute To Onsite	M1_TASK_LOG/ M1_TASK_MOB_LOG.L OG_DTTM	This field is populated based on the time it took to travel until the crew arrived on site (based on the difference between the maximum log date time for the entry with 'En Route' status and the entry with 'Arrived' or 'Onsite' status).
			If there are no log records, it is populated as '0'.
COMPLETED_RESP_ DUR	Response Time to Complete	M1_TASK_LOG/ M1_TASK_MOB_LOG.L OG_DTTM	This field is populated based on the time it took for the crew to arrive on site and finish the task (based on the difference between the maximum log date time for the entry with 'Arrived' or 'Onsite' and the entry with 'Work Done' or 'Completed' status).
			If there are no log records, it is populated as '0'.
TOT_RESP_DUR	P_DUR Total Response Time M1_TASK.DISPATCH_RE SP_DUR  M1_TASK.ENROUTE_R ESP_DUR	This field is populated with the total time it took to complete the task, starting from the time the task was dispatched all the way to the time the task was	
		M1_TASK.ARRIVAL_RES P_DUR	completed.
		M1_TASK.COMPLETED _RESP_DUR	
ACT_TRAVEL_DUR	Actual Travel Duration	M1_TASK_LOG/ M1_TASK_MOB_LOG.L OG_DTTM	This field is populated based on the total time the crew spent travelling to the site. Unit of measure is seconds.
FACT_CNT	Count		This field is populated with the standard value of '1'.
Degenerate Dimensions			
EMERGENCY_IND	Emergency Indicator	M1_TASK.QUEUE_FLG	This field is populated from the source Task table based on the identified tasks. If the Queue Flag is set to 'M1ER', then populate the Emergency Indicator with '1'. Else, with '0'.

Target Field	Description	Source Field	Transformation Logic
APPOINTMENT_IND	Appointment Indicator	M1_TASK.APPOINTME NT_FLG	This field is populated from the source Task table based on the identified tasks. If the Appointment Flag is set to 'Y', then populate the Appointment Indicator with '1'. Else, with '0'.
SAME_DAY_APPT_IND	Same Day Appointment	M1_TASK_TM_WIND.TS K_TM_WIND_START_D TTM M1_TASK.CRE_DTTM	This field is populated with '1' if the appointment is made on the same day as the creation date. Else, with '0'.
TASK_INFO	Task Info String	M1_TASK_TYPE_L.DES CR M1_TASK_ADDR.ADDR ESS1, CITY, COUNTY, STATE	This field is populated with the concatenation of task type description, address, status code, task time window and crew for a task.
		F1_BUS_OBJ_STATUS_L. DESCR	
CRE_DTTM	Create Date/Time	M1_TASK.CRE_DTTM	
STATUS_DTTM	Status Date/Time	M1_TASK.STATUS_UPD _DTTM	
SCHED_START_DTTM	Scheduled Start Date/Time	M1_TASK_TM_WIND.TS K_TM_WIND_START_D TTM	This field is populated with '1' if the appointment is made on the same day as the window start date. Else, with '0'.
SCHED_END_DTTM	Scheduled End Date/Time	M1_TASK_TM_WIND.TS K_TM_WIND_END_DT TM	This field is populated with '1' if the appointment is made on the same day as the window end date. Else, with '0'.
Foreign Keys			
TASK_BO_STATUS_KEY	Task BO Status Dimension Surrogate Key	M1_TASK.BUS_OBJ_CD M1_TASK.BO_STATUS_ CD	This field is populated based on the business object code, status code, and status reason code from the Task table.
		M1_TASK.BO_STATUS_R EASON_CD	
TASK_TYPE_KEY	Task Type Dimension Surrogate Key	M1_TASK.TASK_TYPE_ CD	
SERVICE_AREA_KEY	Service Area Dimension Surrogate Key	M1_TASK.SVC_AREA_C D	

Target Field	Description	Source Field	Transformation Logic
ADDR_KEY	Address Dimension Surrogate Key	M1_TASK_ADDR.ADDR ESS1	This field is populated based on the location of the task.
		M1_TASK_ADDR.ADDR ESS2	
		M1_TASK_ADDR.ADDR ESS3	
		M1_TASK_ADDR.ADDR ESS4	This field is populated based
		M1_TASK_ADDR.CROSS _STREET	
		M1_TASK_ADDR.SUBUR B	'Y
		M1_TASK_ADDR.CITY	
		M1_TASK_ADDR.COUN TY	
		M1_TASK_ADDR.STATE	
		M1_TASK_ADDR.POSTA L	
		M1_TASK_ADDR.COUN TRY	
CREW_KEY	Crew Dimension Surrogate Key	M1_CREW_SHFT.RESRC _ID	the Crew table based on the
			the Crew Shift table for the child task with 'Dispatched' status and with maximum log
APPT_TM_KEY	Appointment Time Dimension Surrogate Key	M1_TASK_TM_WIND.TS This field is K_TM_WIND_START_D on the diffe	on the difference (in minutes) between the appointment start
		M1_TASK_LOG/ M1_TASK_MOB_LOG.L OG_DTTM	date time and log date time.
APPT_TM_OF_DAY_KEY	Appointment Time Of Day Dimension Surrogate Key	M1_TASK_TM_WIND.TS K_TM_WIND_START_D TTM	This field is populated based on the task time window start date/time associated with the task ID.

Target Field	Description	Source Field	Transformation Logic
WORK_DUR_DEV_KEY	Work Duration Deviation Key	M1_TASK_TYPE.ACT_W ORK_DUR M1_TASK_TYPE.EST_W	This field fetches the actual work duration and estimated work duration and calculates the percentage of deviation.
		ORK_DUR	((Actual Work Duration - Estimated Work Duration)/ Estimated Work Duration))*100
RESP_TM_DEV_KEY	Response Time Deviation Dimension Surrogate Key	M1_TASK_TYPE.TOT_R ESP_DUR	This field is populated based on the response time SLA from the Task Type table.
		M1_TASK_TYPE.BO_DA TA_AREA	((Overall Response Time - Response Time SLA)/ Response Time SLA))*100
CRE_DATE_KEY	Creation Date Key	M1_TASK.CRE_DTTM	This field is populated based on the creation date of the task
STATUS_DATE_KEY	Status Date Key	M1_TASK.STATUS_UPD _DTTM	This field is populated based on the status update date of the task.
SCHED_START_DATE_ KEY	Scheduled Start Date Key	M1_TASK_TM_WIND.TS K_TM_WIND_START_D TTM	This field is populated based on the scheduled start date of the task.
SCHED_END_DATE_ KEY	Scheduled End Date Key	M1_TASK_TM_WIND.TS K_TM_WIND_END_DT TM	This field is populated based on the scheduled end date of the task.
CRE_TIME_KEY	Creation Time Key	M1_TASK.CRE_DTTM	This field is populated based on the creation date/time of the task.
STATUS_TIME_KEY	Status Time Key	M1_TASK.STATUS_UPD _DTTM	This field is populated based on the status update date/time of the task.
SCHED_START_TIME_ KEY	Scheduled Start Time Key	M1_TASK_TM_WIND.TS K_TM_WIND_START_D TTM	This field is populated based on the scheduled start time of the task.
SCHED_END_TIME_ KEY	Scheduled End Time Key	M1_TASK_TM_WIND.TS K_TM_WIND_DATE_DT TM	This field fetches the most recent effective time window based on the appointment.
MTR_DEVICE_KEY	Device Dimension Surrogate Key	M1_TASK.BO_DATA_AR EA	This field is populated based on the external identifier value for meter device stored on the task as part of MWM-MDM integration.

Target Field	Description	Source Field	Transformation Logic
SP_KEY	Service Point Dimension Surrogate Key	M1_TASK.BO_DATA_AR EA	This field is populated based on the service point ID stored on the task as part of MWM-MDM integration.
US_KEY	Usage Subscription Dimension Surrogate Key	M1_TASK.BO_DATA_AR EA	This field is populated based on the usage subscription ID stored on the task as part of MWM-MDM integration.
CONTACT_KEY	Contact Dimension Surrogate Key	M1_TASK.BO_DATA_AR EA	This field is populated based on the contact subscription ID stored on the task as part of MWM-MDM integration.
PER_KEY	Person Dimension Surrogate Key	M1_TASK.BO_DATA_AR EA	This field is populated based on the person subscription ID stored on the task as part of MWM-MDM integration.
ACCT_KEY	Account Dimension Surrogate Key	M1_TASK.BO_DATA_AR EA	This field is populated based on the account ID stored on the task as part of MWM-MDM integration.
SA_KEY	Service Agreement Dimension Surrogate Key	M1_TASK.BO_DATA_AR EA	This field is populated based on the service agreement ID stored on the task as part of MWM-MDM integration.
PREM_KEY	Premise Dimension Surrogate Key	M1_TASK.BO_DATA_AR EA	This field is populated based on the premise ID stored on the task as part of MWM-MDM integration.
FLD_ACTIVITY_UDD1_ KEY	Activity User Defined Dimension 1 Key		
FLD_ACTIVITY_UDD2_ KEY	Activity User Defined Dimension 2 Key		
User Defined Attributes			
UDM1	User Defined Measure 1		
UDM2	User Defined Measure 2		
UDM3	User Defined Measure 3		
UDM4	User Defined Measure 4		
UDM5	User Defined Measure 5		
UDM6	User Defined Measure 6		
UDM7	User Defined Measure 7		
UDM8	User Defined Measure 8		
UDM9	User Defined Measure 9		

Target Field	Description	Source Field	Transformation Logic
UDM10	User Defined Measure 10		
UDDGEN1	User Defined Degenerate Dimension 1		
UDDGEN2	User Defined Degenerate Dimension 2		
UDDGEN3	User Defined Degenerate Dimension 3		
UDDGEN4	User Defined Degenerate Dimension 4		
UDDGEN5	User Defined Degenerate Dimension 5		
UDDGENL1	User Defined Long Degenerate Dimension 1		
UDDGENL2	User Defined Long Degenerate Dimension 2		
UDDGENL3	User Defined Long Degenerate Dimension 3		
UDDGENL4	User Defined Long Degenerate Dimension 4		
UDDGENL5	User Defined Long Degenerate Dimension 5		
UDDFK1_KEY	User Defined Dimension Foreign Key 1		
UDDFK2_KEY	User Defined Dimension Foreign Key 2		
UDDFK3_KEY	User Defined Dimension Foreign Key 3		
UDDFK4_KEY	User Defined Dimension Foreign Key 4		
UDDFK5_KEY	User Defined Dimension Foreign Key 5		
Data Load Attributes			
DATA_SOURCE_IND	Data Source Indicator	CI_INSTALLATION.ENV _ID	This field is populated with the DSI value on the source product instance configuration. This table is populated as part of the initial setup and the DSI value is extracted from the environment ID of the source system.

Target Field	Description	Source Field	Transformation Logic
JOB_NBR	Job Number		This field is populated with the ODI job execution session number.