# Oracle Cloud Native Environment Oracle Container Host for Kubernetes Image Builder for Release 2





Oracle Cloud Native Environment Oracle Container Host for Kubernetes Image Builder for Release 2,

G17139-05

Copyright © 2024, 2025, Oracle and/or its affiliates.

Documentation License
The content in this document is licensed under the <u>Creative Commons Attribution—Share Alike 4.0</u> (CC-BY-SA) license. In accordance with CC-BY-SA, if you distribute this content or an adaptation of it, you must provide attribution to Oracle and retain the original copyright notices.

# Contents

Preface	
Introduction	
Installation	
Command Reference	
Build OCK Images	
The ock-forge Script	
Configuration Files	
Partition Layout	
Building OCK Images Examples	
OCK Builder Utilities	



# **Preface**

This document includes information on the Oracle Container Host for Kubernetes Image Builder (OCK Image Builder). This is a tool that builds bootable media for Oracle Container Host for Kubernetes (OCK), based on a treefile configuration.

# Introduction

Describes the Oracle Container Host for Kubernetes Image Builder utility.

The Oracle Container Host for Kubernetes Image Builder (OCK Image Builder) is a tool that builds Oracle Container Host for Kubernetes (OCK) images for Oracle Cloud Native Environment (Oracle CNE) deployments.

For more information about OCK images, see <u>Oracle Cloud Native Environment: Kubernetes</u> Clusters.

Use OCK Image Builder to build custom OCK images for situations where the standard OCK image isn't adequate. For example, consider creating a custom OCK image if you require:

- A different partition layout to the standard OCK image partition layout.
- Extra packages not included in the standard OCK image.
- Device drivers for devices that aren't available in the standard OCK image.

OCK Image Builder consists of a set of shell scripts, the main one of which is ock-forge, and image-specific configuration files that can be used and edited as necessary.

For a specific configuration, OCK Image Builder can generate:

- A bootable Qcow2 image, to create cluster nodes.
- An OSTree container image, which Oracle CNE uses to update nodes in a running cluster.

OCK images are configured using rpm-ostree treefiles and therefore require knowledge of <a href="OSTree">OSTree</a> and <a href="rpm-ostree">rpm-ostree</a>.

For more information about OCK Image Builder, see the OCK Image Builder GitHub repository.

# Installation

Install the OCK Image Builder utility on an Oracle Linux 9 host.

OCK Image Builder must be installed on Oracle Linux 9, from the OCK Image Builder GitHub repository. The prerequisites are Podman, and the <code>qemu-img</code> utility.

1. Install Podman.

```
sudo dnf install container-tools
```

For more information on installing and using Podman, see the <u>Oracle Linux: Podman User's Guide</u>.

2. Install gemu-img.

The qemu-img utility is used to manipulate Qcow2 images. Install qemu-ing from the olg\_kvm\_utils repository.

First, enable the repository:

```
sudo dnf config-manager --enable ol9 kvm utils
```

Then, install gemu-img:

sudo dnf install qemu-img

3. Install Git.

Install the Git client:

```
sudo dnf install git
```

4. Install OCK Image Builder.

Clone the OCK Image Builder GitHub repository:

```
git clone https://github.com/oracle-cne/ock-forge
```

5. Install the OCK Configuration files:

Clone the OCK Configuration GitHub repository. The examples in this guide assume that the configuration files are in the configs directory within the OCK Image Builder installation, so perform the clone from within the ock-forge directory.

```
cd ock-forge
git clone https://github.com/oracle-cne/ock
```

6. Load the nbd kernel module.

OCK Image Builder can generate a bootable OCK image in Qcow2 format, as a raw disk image, or directly to a physical disk. The ock-forge utility mounts Qcow2 images on a



Network Block Device (NBD). Raw disk images are mounted either to a physical disk, or a loopback device, depending on the options specified.

So that OCK Image Builder can mount Qcow2 images to an NBD, load the  ${\tt nbd}$  kernel module:

sudo modprobe nbd max\_part=max\_partitions

Change *max\_partitions* to the maximum number of partitions the resulting Qcow2 image requires. The default is 8, which is enough for most images.

# Command Reference

Command reference for the ock-forge utility.

The ock-forge utility builds bootable media and OSTree container images for OCK, based on an rpm-ostree treefile configuration.

```
ock-forge
[\{-s|--source\}\ URI]
[{-b|--branch} branch-name]
[{-d|--device} block-device]
[{-D|--disk} image-path]
[{-f|--filesystem} filesystem]
[{-i|--image} container-image]
[\{-s|--source\}\ URI]
[{-b|--branch}]
[{-C|--configs-dir} path]
[{-c|--config-dir} path]
[\{-o|--os-name\}] name]
[{-0|--ostree-image-path} path]
[{-n|--no-clean}]
[{-P}|--partition}]
[{-p|--provider} ignition-provider]
[\{-I|--iqnition\}\ path]
[{-B|--build-image} container-image]
[[--karq key=value]...]
[[--karg-append key=value]...]
[[--karg-delete key=value]...]
```

### Where:

### {-s|--source} URI

The path to either a Git repository or a directory. The contents of the location is copied to the build directory. If this option is omitted, the default configuration is used.

### {-b|--branch} branch-name

The name of a Git branch. If this option is provided, the indicated branch is cloned. Without this option, the default branch is cloned.

## {-d|--device} block-device

The path to an existing block device. This device is the installation target. All operations performed by OCK Image Builder are run against this device.

### {-D|--disk} image-path

The path to a disk image file. This value is only necessary if the installation target is a file rather than a raw device. The disk image file is attached to the device specified with the --device option.

### {-f|--filesystem} filesystem

The file system to use when formatting the root partition. This must be xfs.



### {-i|--image} container-image

A fully qualified container image name, including a tag. This argument is used in several ways. If provided alone, this container image is used as the base image to deploy the OS. In this case, building the OSTree is skipped entirely. If provided with the --config-dir option, and the --ostree-image-path option, it generates an OSTree container image that can be used for later installations or upgrades.

### {-s|--source} URI

The URI of an OCK configuration. The configuration is copied from this location into the value of the --configs-dir argument. If the URI ends with .git, the assumption is that it refers to a Git repository. Otherwise, the URI is assumed to be a directory on the local file system.

### {-b|--branch}

If --source refers to a Git repository, the specified branch is checked out after cloning.

### {-C|--configs-dir} path

A directory containing a set of rpm-ostree configurations.

### {-c|--config-dir} path

A directory containing the rpm-ostree configuration to build. This must be a subdirectory of --configs-dir, at whatever depth is required to ensure all symlinks can be resolved. If this option is specified, a complete rpm-ostree build is performed and optionally packaged into an Open Container Initiative (OCI) archive.

### $\{-o|--os-name\}$ name

The name of the OSTree deployment.

### {-0|--ostree-image-path} path

The path to write the Open Container Initiative (OCI) archive generated by the installation process. If this value isn't specified, no archive is generated. If the --config-dir option isn't provided, this option is ignored. If the --image option is provided and points to a valid OSTree container image, it's used as the reference for generating a chunked image.

### {-n|--no-clean}

If this option is provided, don't perform any post install cleanup steps such as unmounting partitions, or detaching virtual block devices.

### {-P|--partition}

If this option is provided, the block device specified using the --device option has its partition table wiped and repopulated with the default geometry.

### {-p|--provider} ignition-provider

Sets the ignition provider. The default value is qemu, unless the --ignition option is used, in which case the default value is file.

This can also be set to oci when creating images for OCI. The oci provider reads Ignition information from the metadata user\_data key/value pair in the Instance metadata service, when creating a compute instance.

### {-I|--ignition} path

The path to an ignition file, which ock-forge can install directly to the boot disk. This is the complete ignition file from the output of an ocne cluster start or ocne cluster join command. The file is embedded into the initramfs on the deployment. If the --provider option isn't specified, the --provider option is set to file.



### {-B|--build-image} container-image

The name of a container image to use when building the OCK boot media. The default value is ock-builder:latest.

### --karg key=value

Set a kernel argument to pass to the ostree command. This overrides any existing argument with the same key. See the ostree-admin-deploy(1) man page for usage. Each kernel argument requires a separate --karg option.

### --karg-append key=value

Append a kernel argument to pass to the ostree command. See the ostree-admin-deploy(1) man page for usage. Each kernel argument appended requires a separate --karg-append option.

### --karg-delete key=value

Delete an existing kernel argument to the <code>ostree</code> command. See the <code>ostree-admin-deploy(1)</code> man page for usage. Each kernel argument deleted requires a separate <code>--karg-delete</code> option.

# **Build OCK Images**

Learn how to use the OCK Image Builder's ock-forge utility to build custom images.

This chapter contains information and examples for building OCK images with the ock-forge utility.

# The ock-forge Script

Describes the capabilities of the ock-forge shell script.

The primary component of OCK Image Builder is the ock-forge script. The ock-forge script generates a bootable OCK image from an rpm-ostree treefile. It requires that the target is a single block device using the standard partition layout. For more information, see Partition Layout.



### NOT SUPPORTED

Although the ock-forge script can build an image from any arbitrary treefile, it's only intended for use with OCK images.

The ock-forge script can output generated images in three different formats:

- A Qcow2 image.
- A Raw ISO image.
- To a block device (physical disk).

In addition to generating the bootable image, ock-forge creates an OSTree container image. This container image is used by Oracle CNE to update nodes in a running cluster.

# **Configuration Files**

Describes OCK image configuration files.

The ock-forge script requires an rpm-ostree treefile configuration that specifies what the generated image contains. Because the script generates OCK images that are intended for Oracle CNE deployments, the treefile must contain the base configuration that's required to work in that environment. These configuration files are available for different target Kubernetes versions in the OCK Configuration GitHub repository.

We recommend that you don't edit these configuration files directly, but include any custom configuration in separate files. This prevents custom configuration from being overwritten by future updates to the OCK image configuration files.



The initial configuration file that the ock-forge script reads is called manifest.yaml. Use an existing configuration for the target Kubernetes version and customize it by including extra configuration files in the manifest.yaml file as follows:

```
# manifest.yaml
include:
- base.yaml
- ux.yaml
- ocne.yaml
- removals.yaml
- custom/myconfig.yaml
...
```

For example, to make the Vim editor available in the custom OCK image, add the following to the myconfig.yaml file:

```
packages:
- vim
```

For more information on the available parameters in an rpm-ostree treefile, see the <u>rpm-ostree</u> <u>Treefile reference</u>.

# **Partition Layout**

Describes the standard partition layout required by OCK images.

Installing to a disk with existing partitions requires at least the following partitions:

- An EFI partition.
- A boot partition labelled boot.
- A root partition labelled root.

We recommend the disk contains only these three partitions and that the root partition is the last partition on the disk. The root partition must be last so that the partition can be automatically expanded to fill the entire disk when the OS boots for the first time. Other layouts are possible, but these have limited applicability and require a good understanding of how partitions are laid out and used.

# **Building OCK Images Examples**

Provides examples of using the ock-forge script to build OCK images.

### Example 4-1 Building a typical Qcow2 image

A typical invocation builds Qcow2 images. The ock-forge script does all the work required. This example generates a new Qcow2 image, attaches it as a block device, partitions the disk, formats the partitions, installs the OS, and generates an OSTree archive:

```
sudo ./ock-forge -d /dev/nbd0 -D out/1.32/boot.qcow2 \
    -i container-registry.oracle.com/olcne/ock-ostree:1.32 \
    -0 ./out/1.32/archive.tar \
    -C ./ock -c configs/config-1.32 -P
```



### Example 4-2 Building a Qcow2 image from GitHub

The ock-forge script can copy configurations from inconvenient places to more convenient places. This example builds a Qcow2 and OSTree image from scratch, using the OCK GitHub repository as a source of truth. The clone of the repository is retained and can be reused in later invocations:

```
sudo ./ock-forge -d /dev/nbd0 -D out/1.32/boot.qcow2 \
    -i container-registry.oracle.com/olcne/ock-ostree:1.32 \
    -0 ./out/1.32/archive.tar \
    -C ./ock -c configs/config-1.32 \
    -s https://github.com/oracle-cne/ock.git -P
```

### Example 4-3 Build a raw disk image

This example generates a raw disk image, rather than a Qcow2 image. The generated image can be dd'ed onto a physical disk, and used to boot a system directly:

```
sudo ./ock-forge -d /dev/loop0 -D out/1.32/boot.iso \
   -i container-registry.oracle.com/olcne/ock-ostree:1.32 \
   -0 ./out/1.32/archive.tar \
   -C ./ock -c configs/config-1.32 -P
```

### Example 4-4 Install to a physical disk

This example installs the image to a physical block device, creating the necessary partitions:

```
sudo ./ock-forge -d /dev/sdb \
    -i container-registry.oracle.com/olcne/ock-ostree:1.32 \
    -0 ./out/1.32/archive.tar \
    -C ./ock -c configs/config-1.32 -P
```

### Example 4-5 Install but don't generate OSTree archive

This example performs a fresh installation of the OS, but doesn't store the contents in an OSTree container image archive:

```
sudo ./ock-forge -d /dev/nbd0 -C ./ock -c configs/config-1.32 -P
```

### Example 4-6 Install from a container image

This example installs the OS using an existing OSTree container image as the source:

```
sudo ./ock-forge -d /dev/nbd0 -d /dev/loop0 -D out/1.32/boot.iso \
    -i container-registry.oracle.com/olcne/ock-ostree:1.32 -P
```

# **OCK Builder Utilities**

Lists the individual scripts that the OCK Image Builder tool consists of.

The ock-forge utility is a shell script that relies on other shell scripts to do its work. Each of the shell scripts can be useful by itself, but probably requires editing to make it so.



### Warning

Ensure that you understand how these scripts function before changing them. These utility scripts can be destructive if used incorrectly.

The shell scripts that make up the OCK Image Builder tool are listed in the following table.

Table 5-1 OCK Image Builder Utility Scripts

Script	Options	Notes
setup-vm-disk.sh	-d network-block-device -D path-to-new-image	Creates a Qcow2 image and attaches it to a network block device.
sparsify-image.sh	-D path-to-image	Re-sparsifies and compresses a Qcow2 image. It does part of the job of virt-sparsify and the result isn't as good.  However, it has the advantage of not requiring a VM and can be used in environments where starting a VM isn't an option. For example, building an image inside an ARM VM. It requires several gigabytes of storage while running. That space is released by the time the script ends.
make-partitions.sh	-d path-to-device	Partitions a disk using a standard layout. It creates a small EFI partition as partition 1, a small boot partition as partition 2, and a root partition with the rest of the disk as the last partition.
	-f filesystem	

### Example 5-1 Creating and attaching Qcow2 images

To create a Qcow2 image and attach it to /dev/nbd0:

sudo ./setup-vm-disk -d /dev/nbd0 -D mydisk.qcow2



### Example 5-2 Sparsify a Qcow2 image

To sparsify and compress an existing Qcow2 image:

sudo ./sparsify-image.sh -D mydisk.qcow2

### **Example 5-3** Partition a disk

To partition a physical block device using XFS:

sudo ./make-partitions.sh -d /dev/sdb -f xfs