

**Oracle® ZFS Storage Appliance Object
API Guide for Oracle Cloud Infrastructure
Object Storage Service Support, Release
OS8.8.x**

ORACLE®

Part No: F21262-02
August 2021

Part No: F21262-02

Copyright © 2019, 2021, Oracle and/or its affiliates.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs (including any operating system, integrated software, any programs embedded, installed or activated on delivered hardware, and modifications of such programs) and Oracle computer documentation or other Oracle data delivered to or accessed by U.S. Government end users are "commercial computer software" or "commercial computer software documentation" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, reproduction, duplication, release, display, disclosure, modification, preparation of derivative works, and/or adaptation of i) Oracle programs (including any operating system, integrated software, any programs embedded, installed or activated on delivered hardware, and modifications of such programs), ii) Oracle computer documentation and/or iii) other Oracle data, is subject to the rights and limitations specified in the license contained in the applicable contract. The terms governing the U.S. Government's use of Oracle cloud services are defined by the applicable contract for such services. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Inside are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Epyc, and the AMD logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc>.

Access to Oracle Support

Oracle customers that have purchased support have access to electronic support through My Oracle Support. For information, visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info> or visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs> if you are hearing impaired.

Référence: F21262-02

Copyright © 2019, 2021, Oracle et/ou ses affiliés.

Ce logiciel et la documentation qui l'accompagne sont protégés par les lois sur la propriété intellectuelle. Ils sont concédés sous licence et soumis à des restrictions d'utilisation et de divulgation. Sauf stipulation expresse de votre contrat de licence ou de la loi, vous ne pouvez pas copier, reproduire, traduire, diffuser, modifier, accorder de licence, transmettre, distribuer, exposer, exécuter, publier ou afficher le logiciel, même partiellement, sous quelque forme et par quelque procédé que ce soit. Par ailleurs, il est interdit de procéder à toute ingénierie inverse du logiciel, de le désassembler ou de le décompiler, excepté à des fins d'interopérabilité avec des logiciels tiers ou tel que prescrit par la loi.

Les informations fournies dans ce document sont susceptibles de modification sans préavis. Par ailleurs, Oracle Corporation ne garantit pas qu'elles soient exemptes d'erreurs et vous invite, le cas échéant, à lui en faire part par écrit.

Si ce logiciel, ou la documentation qui l'accompagne, est livré sous licence au Gouvernement des Etats-Unis, ou à quiconque qui aurait souscrit la licence de ce logiciel pour le compte du Gouvernement des Etats-Unis, la notice suivante s'applique :

U.S. GOVERNMENT END USERS: Oracle programs (including any operating system, integrated software, any programs embedded, installed or activated on delivered hardware, and modifications of such programs) and Oracle computer documentation or other Oracle data delivered to or accessed by U.S. Government end users are "commercial computer software" or "commercial computer software documentation" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, reproduction, duplication, release, display, disclosure, modification, preparation of derivative works, and/or adaptation of i) Oracle programs (including any operating system, integrated software, any programs embedded, installed or activated on delivered hardware, and modifications of such programs), ii) Oracle computer documentation and/or iii) other Oracle data, is subject to the rights and limitations specified in the license contained in the applicable contract. The terms governing the U.S. Government's use of Oracle cloud services are defined by the applicable contract for such services. No other rights are granted to the U.S. Government.

Ce logiciel ou matériel a été développé pour un usage général dans le cadre d'applications de gestion des informations. Ce logiciel ou matériel n'est pas conçu ni n'est destiné à être utilisé dans des applications à risque, notamment dans des applications pouvant causer un risque de dommages corporels. Si vous utilisez ce logiciel ou matériel dans le cadre d'applications dangereuses, il est de votre responsabilité de prendre toutes les mesures de secours, de sauvegarde, de redondance et autres mesures nécessaires à son utilisation dans des conditions optimales de sécurité. Oracle Corporation et ses affiliés déclinent toute responsabilité quant aux dommages causés par l'utilisation de ce logiciel ou matériel pour des applications dangereuses.

Oracle et Java sont des marques déposées d'Oracle Corporation et/ou de ses affiliés. Tout autre nom mentionné peut correspondre à des marques appartenant à d'autres propriétaires qu'Oracle.

Intel et Intel Inside sont des marques ou des marques déposées d'Intel Corporation. Toutes les marques SPARC sont utilisées sous licence et sont des marques ou des marques déposées de SPARC International, Inc. AMD, Epyc, et le logo AMD sont des marques ou des marques déposées d'Advanced Micro Devices. UNIX est une marque déposée de The Open Group.

Ce logiciel ou matériel et la documentation qui l'accompagne peuvent fournir des informations ou des liens donnant accès à des contenus, des produits et des services émanant de tiers. Oracle Corporation et ses affiliés déclinent toute responsabilité ou garantie expresse quant aux contenus, produits ou services émanant de tiers, sauf mention contraire stipulée dans un contrat entre vous et Oracle. En aucun cas, Oracle Corporation et ses affiliés ne sauraient être tenus pour responsables des pertes subies, des coûts occasionnés ou des dommages causés par l'accès à des contenus, produits ou services tiers, ou à leur utilisation, sauf mention contraire stipulée dans un contrat entre vous et Oracle.

Accessibilité de la documentation

Pour plus d'informations sur l'engagement d'Oracle pour l'accessibilité de la documentation, visitez le site Web Oracle Accessibility Program, à l'adresse : <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc>.

Accès aux services de support Oracle

Les clients Oracle qui ont souscrit un contrat de support ont accès au support électronique via My Oracle Support. Pour plus d'informations, visitez le site <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info> ou le site <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs> si vous êtes malentendant.

Contents

Oracle ZFS Storage Appliance Object API for Oracle Cloud Infrastructure Object Storage	7
Using the Oracle Cloud Infrastructure Object Storage Service	7
▼ Enabling the Oracle Cloud Infrastructure Object Storage Service (BUI)	8
▼ Enabling the Oracle Cloud Infrastructure Object Storage Service (CLI)	8
▼ Managing Oracle Cloud Infrastructure Object Storage Service User Keys (BUI)	9
▼ Managing Oracle Cloud Infrastructure Object Storage Service User Keys (CLI)	11
▼ Configuring the Oracle Cloud Infrastructure Object Storage Service (BUI)	13
▼ Configuring the Oracle Cloud Infrastructure Object Storage Service (CLI)	15
Oracle ZFS Storage Appliance RESTful API Support for the Oracle Cloud Infrastructure Object Storage Service	17
List Oracle Cloud Infrastructure Service Details	17
Enable the Oracle Cloud Infrastructure Service	19
List Oracle Cloud Infrastructure Keys	19
Create a New Oracle Cloud Infrastructure User Key	20
Change Operations Permissions for an Oracle Cloud Infrastructure User Key	21
Delete an Oracle Cloud Infrastructure User Key	22
Set the Oracle Cloud Infrastructure Default Path	23
Supported Oracle Cloud Infrastructure Object Storage API Capabilities	24
Listing Namespaces	24
Managing Buckets	25
Managing Objects	25
Multipart Upload	26
Managing Pre-authenticated Requests	26
Managing Retention Rules	27

Oracle ZFS Storage Appliance Object API for Oracle Cloud Infrastructure Object Storage

Oracle ZFS Storage Appliance object API for Oracle Cloud Infrastructure Object Storage enables you to use the same applications both on-premises on Oracle ZFS Storage Appliance and in the cloud on Oracle Cloud Infrastructure Object Storage. Applications that are written to store content on Oracle Cloud Infrastructure Object Storage can also be used to store content on Oracle ZFS Storage Appliance on-premises with no modification of the application.

The appliance API for Oracle Cloud Infrastructure objects supports a subset of the Oracle Cloud Infrastructure Object Storage API, as described in [“Supported Oracle Cloud Infrastructure Object Storage API Capabilities”](#) on page 24.

This guide describes the following steps to configure Oracle Cloud Infrastructure Object Storage on an appliance:

- Enable the Oracle Cloud Infrastructure Object Storage service.
- Create and upload a user’s key for signature authentication.
Create an RSA-SHA256 private/public key pair for each user, and then upload the public key to the appliance.
Each request contains a signature that is generated from the private key used by the client and authenticated with the public key on the appliance. For more information, see [Required Keys and OCIDs](#).
- Configure the service for specific projects and filesystems.
Define an appliance filesystem to be used as an endpoint to store objects. Enable the Oracle Cloud Infrastructure HTTP protocol as read/write.

Using the Oracle Cloud Infrastructure Object Storage Service

See the following topics to configure an appliance to operate on Oracle Cloud Infrastructure Object Storage objects:

- Enabling the Oracle Cloud Infrastructure Object Storage Service - [BUI](#), [CLI](#)
- Managing Oracle Cloud Infrastructure Object Storage Service User Keys - [BUI](#), [CLI](#)
- Configuring the Oracle Cloud Infrastructure Object Storage Service - [BUI](#), [CLI](#)
- “Oracle ZFS Storage Appliance RESTful API Support for the Oracle Cloud Infrastructure Object Storage Service” on page 17

▼ Enabling the Oracle Cloud Infrastructure Object Storage Service (BUI)

This procedure describes how to use the BUI to enable the Oracle Cloud Infrastructure Object Storage service for the HTTP protocol.

1. **Go to Configuration > Services.**
2. **Under Data Services, click HTTP.**
3. **Click the OCI tab.**
4. **In the OCI API section, click the Enable OCI checkbox to enable the Oracle Cloud Infrastructure Object Storage service for the HTTP protocol.**
If the Enable OCI checkbox is checked, clicking the checkbox disables the service.
5. **Click APPLY.**
6. **Verify the Default path property value.**

The Default path property specifies the default location to store your objects. This Default path is used if you do not specify the location for an object when you use the Oracle Cloud Infrastructure object store.

The value of this property is the mountpoint of a filesystem that has the OCI API mode set to Read/write as described in “[Configuring the Oracle Cloud Infrastructure Object Storage Service \(BUI\)](#)” on page 13.

▼ Enabling the Oracle Cloud Infrastructure Object Storage Service (CLI)

This procedure describes how to use the CLI to enable the Oracle Cloud Infrastructure Object Storage service for the HTTP protocol.

1. **Go to the oci node of the http service.**

```
hostname:> configuration services http oci
```

2. **(Optional) List the properties of the oci node.**

```
hostname:configuration services http oci> ls
Properties:
    oci_enabled = false
    oci_default_path = /export/ofs1
```

Children:

```
keys => Manage this Keystore's Keys
```

3. **To enable the Oracle Cloud Infrastructure Object Storage service for the HTTP protocol, set the oci_enabled property to true.**

```
hostname:configuration services http oci> set oci_enabled=true
oci_enabled = true (uncommitted)
```

4. **Commit the change.**

```
hostname:configuration services http oci (uncommitted)> commit
```

5. **Verify the oci_default_path property value.**

The `oci_default_path` property specifies the default location to store your objects. This default path is used if you do not specify the location for an object when you use the Oracle Cloud Infrastructure object store.

The value of this property is the mountpoint of a filesystem that has the `shareoci` property set to `rw` as described in [“Configuring the Oracle Cloud Infrastructure Object Storage Service \(CLI\)”](#) on page 15.

▼ Managing Oracle Cloud Infrastructure Object Storage Service User Keys (BUI)

This procedure describes how to use the BUI to create a user key, set operations permissions for a user key, or delete a user key for the Oracle Cloud Infrastructure Object Storage service for the HTTP protocol.

1. **Go to Configuration > Services.**
2. **Under Data Services, click HTTP.**

3. **Click the OCI tab.**

4. **Click the add icon  next to Keys to create a new user key.**

a. **In the New Key dialog box, enter a user name, a public key, and an optional comment.**

The user name is the OCID of an Oracle Cloud Infrastructure account user and is also a valid data user on the appliance. A data user is a user that is allowed to access data protocols. The user does not need to be an appliance administrator.

The public key is a 392-character base64 string that corresponds to an RSA public key in PEM format.


b. **Click ADD.**

The Keys list displays the generated fingerprint for the new key.

- A unique fingerprint is generated for each different key that is entered by the same user.
- The same fingerprint is generated for a key that is entered by different users.

5. **(Optional) Change operations permissions for a user key.**


Permissions control a user's ability to perform operations on resources. See the [Permissions Required for Each API Operation](#) for more information.

a. **Hover over the entry for the key that you want to change, and click the edit icon .**

The Edit Key Permissions dialog box opens.

b. **In the Edit Key Permissions dialog box, check the box to the left of each permission that you want enabled for this user key.**

c. **Click OK.**

6. **To delete a key, hover over the entry for the key you want to delete, and click the trash icon .**

▼ Managing Oracle Cloud Infrastructure Object Storage Service User Keys (CLI)

This procedure describes how to use the CLI to create a user key, set operations permissions for a user key, or delete a user key for the Oracle Cloud Infrastructure Object Storage service for the HTTP protocol.

1. Go to the `oci keys` node of the `http` service.

```
hostname:> configuration services http oci keys
hostname:configuration services http oci keys> list
NAME      CREATED          USER  FINGERPRINT          COMMENT
key-000   2019-6-19 15:25:42  usr1  key-000-fingerprint
key-001   2019-7-8 16:01:18  usr2  key-001-fingerprint
```

2. Use the `create` command to create a new user key.

```
hostname:configuration services http oci keys> create
```

Provide a user name, a public key, and an optional comment.

a. Set the user name.

The user name is the OCID of an Oracle Cloud Infrastructure account user and is also a valid data user on the appliance. A data user is a user that is allowed to access data protocols. The user does not need to be an appliance administrator.

```
hostname:configuration services http oci key-002 (uncommitted)> set user=usr3
user = usr3 (uncommitted)
```

b. Use the `setkey` command to set the key.

The public key is a 392-character base64 string that corresponds to an RSA public key in PEM format. The key is echoed in correct PEM format for visual verification.

```
hostname:configuration services http oci key-002 (uncommitted)> setkey
("." to end)> -----BEGIN PUBLIC KEY-----
("." to end)> MIIBITANBgkqhkiG9w0BAQEFAAOCAQ4AMIIBCQKCAQBqm2f5LP6Ie9Nc6QiA+1Sb
("." to end)> ...
("." to end)> Bg/rj3I097yXax+l8hIwCI6uNzgye7bUSQF6BNyEuNazW8VbCJPwnTdbWknKoSXh
("." to end)> AgMBAAEa
("." to end)> -----END PUBLIC KEY-----
("." to end)> .
```

3. (Optional) Provide a comment.

```
hostname:configuration services http oci key-002 (uncommitted)> set comment=dev
```

```
comment = dev (uncommitted)
```

4. Commit the changes.

```
hostname:configuration services http oci key-002 (uncommitted)> commit
```

Here is the fingerprint associated with the registered public key.

```
Fingerprint: key-002-fingerprint
```

The Keys list displays the generated fingerprint for the new key.

- A unique fingerprint is generated for each different key that is entered by the same user.
- The same fingerprint is generated for a key that is entered by different users.

5. (Optional) Change operations permissions for a user key.

Permissions control a user's ability to perform operations on resources. See the [Permissions Required for Each API Operation](#) for more information.

a. Select a key.

A specific key can be selected in either of the following ways:

- By key name, such as `key-000`.
- By both username and fingerprint. A username or a fingerprint could match more than one key. Even if the username or fingerprint is unique in the current configuration, you must specify both to select the key.

To select a key, use one of the following commands:

```
hostname:configuration services http oci keys> select keyname
hostname:configuration services http oci keys> select user=username
fingerprint=fingerprint
```

Select the new key and show its permissions properties.

```
hostname:configuration services http oci keys> select key-002
hostname:configuration services http oci key-002> ls
Properties:
```

```
    user = usr3
    fingerprint = key-002-fingerprint
    comment = dev
    namespace_read = true
    bucket_create = true
    bucket_update = true
    bucket_read = true
    bucket_inspect = true
    bucket_delete = true
    object_create = true
```

```

object_overwrite = true
  object_read = true
    object_inspect = true
      object_delete = true
object_version_delete = true
  par_manage = true
retention_rule_manage = true
retention_rule_lock = true

```

b. Disable or enable specific permissions.

The following example disables the `object_version_delete` permission for the selected key.

```

hostname:configuration services http oci key-002> set object_version_delete=false
object_version_delete = false (uncommitted)

```

c. Commit the changes.

```

hostname:configuration services http oci key-002> commit
hostname:configuration services http oci key-002> get object_version_delete
object_version_delete = false
hostname:configuration services http oci key-002> done

```

6. To delete a key, use the `destroy` command.

Enter `destroy keyname`, and then enter `Y` to confirm the key deletion.

```

hostname:configuration services http oci keys> destroy key-000
This will delete key "key-000". Are you sure? (Y/N) y

```

▼ Configuring the Oracle Cloud Infrastructure Object Storage Service (BUI)

To configure the Oracle Cloud Infrastructure Object Storage service, enable the Oracle Cloud Infrastructure HTTP protocol as read/write for a filesystem. A filesystem that has the Oracle Cloud Infrastructure HTTP protocol enabled as read/write can be specified as the default namespace used by clients that access the object storage service and do not specify a namespace. See the Default path field in [“Enabling the Oracle Cloud Infrastructure Object Storage Service \(BUI\)” on page 8](#).


Note - OCI API mode can be enabled only if no other share mode is enabled. If OCI API mode is enabled, no other share mode can be enabled. OCI API mode cannot be disabled once it has been enabled.

1. Go to Shares.

You can configure a project and then set the filesystems to inherit that configuration, or you can configure individual filesystems.

2. (Optional) Configure a project.

a. **Click the Projects tab.**

b. **Hover over the entry for the project that you want to configure, and click the edit icon .**


c. **Click the Protocols tab.**

d. **Under HTTP, set the OCI API mode to Read/write.**

e. **Click APPLY.**

3. Configure a filesystem.

a. **Click the Filesystems tab.**

b. **Hover over the entry for the filesystem that you want to configure, and click the edit icon .**

c. **Click the Protocols tab.**

d. **Under HTTP, set the OCI API mode to Read/write.**

Use one of the following methods to specify the OCI API mode:

- **If you performed this configuration on the parent project, click the Inherit from project checkbox.**

Verify that the value of the OCI API mode is Read/write.

Note - If the Inherit from project checkbox is checked, then all of the HTTP modes inherit properties from the parent project.

- **If you did not perform this configuration on the parent project, set the OCI API mode to Read/write.**

Verify that the Inherit from project checkbox is not checked.

Click the OCI API mode dropdown menu and select Read/write.

Note - If the Inherit from project checkbox is not checked, then none of the HTTP modes inherit properties from the parent project.

- e. **Click APPLY.**

▼ **Configuring the Oracle Cloud Infrastructure Object Storage Service (CLI)**

To configure the Oracle Cloud Infrastructure Object Storage service, set the `shareoci` property to read/write for a filesystem. A filesystem that has the `shareoci` property set to read/write can be specified as the default namespace used by clients that access the object storage service and do not specify a namespace. See the `oci_default_path` property in [“Enabling the Oracle Cloud Infrastructure Object Storage Service \(CLI\)” on page 8](#).

Note - OCI API mode can be enabled only if no other share mode is enabled. If OCI API mode is enabled (the `shareoci` property is set to read/write for a filesystem), no other share mode can be enabled. OCI API mode cannot be disabled once it has been enabled.

1. **Go to shares.**

You can configure a project and then set the filesystems to inherit that configuration, or you can configure individual filesystems.

By default, shares inherit all of their properties from their parent project. If a property is changed on a project, all shares on which that property has not been set locally are updated to reflect the new value.
2. **(Optional) Configure a project.**
 - a. **Select the parent project of the filesystem that you want to configure.**

```
hostname:shares (pool1)> select default
```

b. Show the value of the shareoci property.

```
hostname:shares (pool1) default> get shareoci
shareoci = off
```

If the value of the shareoci property is rw, stop, you are finished.

c. Set the shareoci property to rw.

```
hostname:shares (pool1) default> set shareoci=rw
shareoci = rw (uncommitted)
```

d. Commit the change.

```
hostname:shares (pool1) default> commit
```

3. Configure a filesystem.

a. Select the filesystem that you want to configure.

```
hostname:shares (pool1) default> select fs1
```

b. Show the value of the shareoci property.

```
hostname:shares default/fs1> get shareoci
shareoci = off
```

If the value of the shareoci property is rw, stop, you are finished.

c. Set the shareoci property to rw.

```
hostname:shares default/fs1> set shareoci=rw
shareoci = rw (uncommitted)
```

d. Commit the change.

```
hostname:shares default/test1> commit
```


Oracle ZFS Storage Appliance RESTful API Support for the Oracle Cloud Infrastructure Object Storage Service

The following RESTful API requests support the Oracle Cloud Infrastructure Object Storage service.

TABLE 1 RESTful API services Commands to Support the Oracle Cloud Infrastructure Object Storage Service

Request	Append to Path <i>/api/service/v2/services</i>	Description
GET	<i>/http</i>	List http service and sub-service details.
GET	<i>/http/oci</i>	List the Oracle Cloud Infrastructure service details.
PUT	<i>/http/oci</i>	Modify the Oracle Cloud Infrastructure service.
GET	<i>/http/oci/keys</i>	List all Oracle Cloud Infrastructure public keys.
POST	<i>/http/oci/keys</i>	Create a new Oracle Cloud Infrastructure public key.
GET	<i>/http/oci/keys/user/fingerprint</i>	List the specified Oracle Cloud Infrastructure public key.
DELETE	<i>/http/oci/keys/user/fingerprint</i>	Delete the specified Oracle Cloud Infrastructure public key.

TABLE 2 RESTful API pools Commands to Support the Oracle Cloud Infrastructure Object Storage Service

Request	Append to Path <i>/api/storage/v2/pools</i>	Description
GET	<i>/pool/projects/project</i>	List project details, including the value of the <code>shareoci</code> property.
GET	<i>/pool/projects/project/filesystems/filesystem</i>	List filesystem details, including the value of the <code>shareoci</code> property.
PUT	<i>/pool/projects/project</i>	Set the <code>shareoci</code> property for the specified project.
PUT	<i>/pool/projects/project/filesystems/filesystem</i>	Set the <code>shareoci</code> property for the specified filesystem.

List Oracle Cloud Infrastructure Service Details

The following example lists all properties and sub-services of the HTTP service.

Example Request:

```
GET /api/service/v2/services/http
```

Example Result:

Some details are omitted from the following output.

```
{
  "service": {
    "href": "/api/service/v2/services/http",
    ...
    "oci": {
      "href": "/api/service/v2/services/http/oci",
      "oci_enabled": false,
      "oci_default_path": "",
      "keys": [ ... ]
    },
    "s3": { ... },
    "swift": { ... },
    "webdav": { ... }
  }
}
```

The following example lists all properties of the HTTP Oracle Cloud Infrastructure service.

Example Request:

```
GET /api/service/v2/services/http/oci
```

Example Result:

```
{
  "oci": {
    "href": "/api/service/v2/services/http/oci",
    "oci_enabled": false,
    "oci_default_path": "",
    "keys": [
      {
        "user": "user1",
        "comment": "comment"
        "fingerprint": "fingerprint1",
        "href": "/api/service/v2/services/http/oci/keys/user1/fingerprint1"
      },
      {
        "user": "user2",
        "comment": "comment"
        "fingerprint": "fingerprint2",
        "href": "/api/service/v2/services/http/oci/keys/user2/fingerprint2"
      }
    ]
  }
}
```

Enable the Oracle Cloud Infrastructure Service

Example Request:

```
PUT /api/service/v2/services/http/oci
```

```
{ "oci_enabled": true }
```

Example Result:

```
{
  "oci": {
    "href": "/api/service/v2/services/http/oci",
    "oci_enabled": true,
    "oci_default_path": "",
    "keys": [ ... ]
  }
}
```

The `oci_default_path` property specifies the default location to store your objects. This default path is used if you do not specify the location for an object when you use the Oracle Cloud Infrastructure object store.

The value of this property is the mountpoint of a filesystem that has the `shareoci` property set to `rw` as described in [“Set the Oracle Cloud Infrastructure Default Path” on page 23](#).

List Oracle Cloud Infrastructure Keys

The following example lists all Oracle Cloud Infrastructure keys.

Example Request:

```
GET /api/service/v2/services/http/oci/keys
```

Example Result:

```
"keys": [
  {
    "user": "user1",
    "comment": "comment"
    "fingerprint": "fingerprint1",
    "href": "/api/service/v2/services/http/oci/keys/user1/fingerprint1"
  },
  {
    "user": "user2",
    "comment": "comment"
  }
]
```

```
    "fingerprint": "fingerprint2",
    "href": "/api/service/v2/services/http/oci/keys/user2/fingerprint2"
  }
]
```

The following example lists the specified Oracle Cloud Infrastructure key.

Example Request:

```
GET /api/service/v2/services/http/oci/user2/fingerprint2
```

Example Result:

```
{
  "key": {
    "user": "user2",
    "comment": "comment",
    "fingerprint": "fingerprint2",
    "href": "/api/service/v2/services/http/oci/keys/user2/fingerprint2"
  }
}
```

Create a New Oracle Cloud Infrastructure User Key

To create a new user key, enter a user name, a public key, and an optional comment.

The user name is the OCID of an Oracle Cloud Infrastructure account user and is also a valid data user on the appliance. A data user is a user that is allowed to access data protocols. The user does not need to be an appliance administrator.

The public key is a 392-character base64 string that corresponds to an RSA public key in PEM format.

A unique fingerprint is generated for each different key that is entered by the same user.

The same fingerprint is generated for a key that is entered by different users, as shown in the following example.

Example Request:

```
POST /api/service/v2/services/http/oci/keys
```

```
{
  "user": "user3",
  "key" : "-----BEGIN PUBLIC KEY-----\nkey2-text\n-----END PUBLIC KEY-----",
  "comment": "comment"
```

```
}
```

Example Result:

```
{
  "key": {
    "user": "user3",
    "comment": "comment",
    "fingerprint": "fingerprint2",
    "href": "/api/service/v2/services/http/oci/keys/user3/fingerprint2"
  }
}
```

Change Operations Permissions for an Oracle Cloud Infrastructure User Key

Permissions control a user's ability to perform operations on resources. See the [Permissions Required for Each API Operation](#) for more information.

If a user attempts to perform an operation using a key that does not grant permission for that operation, HTTP status 401 (Unauthorized) is returned.

The following request shows the operations permissions for an Oracle Cloud Infrastructure user key.

Example Request:

```
GET /api/service/v2/services/http/oci/keys/user3/fingerprint2
```

Example Result:

```
{
  "key": {
    "href": "/api/service/v2/services/http/oci/keys/user3/fingerprint2",
    "user": "user3",
    "fingerprint": "fingerprint2",
    "comment": "",
    "namespace_read": true,
    "bucket_create": true,
    "bucket_update": true,
    "bucket_read": true,
    "bucket_inspect": true,
    "bucket_delete": true,
    "object_create": true,
    "object_overwrite": true,
    "object_read": true,
  }
}
```

```
    "object_inspect": true,
    "object_delete": true,
    "object_version_delete": true,
    "par_manage": true,
    "retention_rule_manage": true,
    "retention_rule_lock": true
  }
}
```

The following example disables the `object_delete` and `object_version_delete` permissions for the `user3/fingerprint2` key.

Example Request:

```
PUT /api/service/v2/services/http/oci/keys/user3/fingerprint2
```

```
{"object_delete": false, "object_version_delete": false}
```

Example Result:

```
{
  "key": {
    "href": "/api/service/v2/services/http/oci/keys/user3/fingerprint2",
    "user": "user3",
    "fingerprint": "fingerprint2",
    "comment": "",
    "namespace_read": true,
    "bucket_create": true,
    "bucket_update": true,
    "bucket_read": true,
    "bucket_inspect": true,
    "bucket_delete": true,
    "object_create": true,
    "object_overwrite": true,
    "object_read": true,
    "object_inspect": true,
    "object_delete": false,
    "object_version_delete": false,
    "par_manage": true,
    "retention_rule_manage": true,
    "retention_rule_lock": true
  }
}
```

Delete an Oracle Cloud Infrastructure User Key

Example Request:

```
DELETE /api/service/v2/services/http/oci/user2/fingerprint2
```

Set the Oracle Cloud Infrastructure Default Path

The default path is used by clients that access the object storage service and do not specify a namespace. See the `oci_default_path` property in [“Enable the Oracle Cloud Infrastructure Service” on page 19](#). The value of the `oci_default_path` property is the mountpoint of a filesystem that has the `shareoci` property set to `rw`.

You can set the `shareoci` property on a project or on a filesystem. The `shareoci` property setting on a project is inherited by all child filesystems unless you explicitly set the property on the filesystem.

Note - OCI API mode can be enabled only if no other share mode is enabled. If OCI API mode is enabled (the `shareoci` property is set to read/write for a filesystem), no other share mode can be enabled. OCI API mode cannot be disabled once it has been enabled.

The following example shows the value of the `shareoci` property on the `proj1` project.

Example Request:

```
GET /api/storage/v2/pools/p1/projects/proj1 HTTP/1.1
```

Example Result:

```
{
  "project": {
    ...
    "shareoci": "off",
    ...
  }
}
```

The following example shows the value of the `shareoci` property on the `f1` filesystem.

Example Request:

```
GET /api/storage/v2/pools/p1/projects/proj1/filesystems/f1 HTTP/1.1
```

Example Result:

```
{
  "filesystem": {
    ...
    "shareoci": "off",
  }
}
```

```
    ...
  }
}
```

The following example sets the value of the `shareoci` property on the `f1` filesystem.

Example Request:

```
PUT /api/storage/v2/pools/p1/projects/proj1/filesystems/f1 HTTP/1.1
```

```
{ "shareoci": "rw" }
```

Example Result:

```
{
  "filesystem": {
    ...
    "shareoci": "rw",
    ...
  }
}
```

Supported Oracle Cloud Infrastructure Object Storage API Capabilities

The following tables describe the supported Oracle Cloud Infrastructure Object Storage API capabilities for Oracle ZFS Storage Appliance.

The appliance API for Oracle Cloud Infrastructure objects supports a subset of the Oracle Cloud Infrastructure Object Storage API. For full details about Oracle Cloud Infrastructure Object Storage API, including paths, complete descriptions of the requests, descriptions of the parameters, descriptions of all response codes, and examples, see [Object Storage Service API](#). For an overview, see [Overview of Object Storage](#).

Note - No interoperability is supported between Oracle Cloud Infrastructure object APIs and Amazon S3 or Swift object APIs.

Listing Namespaces

A namespace is a unique, uneditable, system-generated string assigned to a tenant during account creation.

Request	Path	Description	Normal Response Code
GET	/n/	(GetNamespace) Lists the name of the Object Storage namespace for the user making the request.	200
GET	/n/namespaceName	(GetNamespaceMetadata) Lists the metadata for the specified Object Storage namespace.	200

Managing Buckets

A bucket is a container for storing objects.

Request	Append to Path /n/namespaceName	Description	Normal Response Code
GET	/b/	(ListBuckets) Lists all buckets that are on the specified namespace.	200
GET	/b/bucketName/	(GetBucket) Gets the specified bucket.	200
HEAD	/b/bucketName/	(HeadBucket) Gets the current entity tag (ETag) of the specified bucket.	200
POST	/b/	(CreateBucket) Creates a standard or archive bucket. No difference for Oracle ZFS Storage Appliance.	200
POST	/b/bucketName/	(UpdateBucket) Updates the user-defined metadata of the specified bucket.	200
DELETE	/b/bucketName/	(DeleteBucket) Deletes an empty bucket.	204

Managing Objects

An object is a set of data with associated metadata.

Request	Append to Path /n/namespaceName	Description	Normal Response Code
GET	/b/bucketName/o	(ListObjects) Lists the objects in the specified bucket.	200
GET	/b/bucketName/objectversions	(ListObjectVersions) Lists the object versions in the specified bucket.	200
GET	/b/bucketName/o/objectName	(GetObject) Gets the metadata and body of the specified object.	200

Request	Append to Path <i>/n/namespaceName</i>	Description	Normal Response Code
HEAD	<i>/b/bucketName/o/objectName</i>	(HeadObject) Gets the user-defined metadata and ETag for the specified object.	200
POST	<i>/b/bucketName/o/actions/copyObject</i>	(CopyObject) Creates a request to copy an object within a region or to another region.	200
PUT	<i>/b/bucketName/o/objectName</i>	(PutObject) Creates a new object or overwrites an existing object with the same name.	200
DELETE	<i>/b/bucketName/o/objectName</i>	(DeleteObject) Deletes an object.	204

Multipart Upload

Individual parts of an object can be uploaded in parallel to reduce upload time.

Request	Append to Path <i>/n/namespaceName</i>	Description	Normal Response Code
GET	<i>/b/bucketName/u</i>	(ListMultipartUploads) Lists all the in-progress multipart uploads for the specified bucket.	200
GET	<i>/b/bucketName/u/objectName</i>	(ListMultipartUploadParts) Lists the parts of an in-progress multipart upload.	200
POST	<i>/b/bucketName/u</i>	(CreateMultipartUpload) Starts a new multipart upload to a specific object in the specified bucket.	200
POST	<i>/b/bucketName/u/objectName</i>	(CommitMultipartUpload) Commits a multipart upload, which involves checking part numbers and ETags of the parts, to create an aggregate object.	200
PUT	<i>/b/bucketName/u/objectName</i>	(UploadPart) Uploads a single part of a multipart upload.	200
DELETE	<i>/b/bucketName/u/objectName</i>	(AbortMultipartUpload) Aborts an in-progress multipart upload and deletes all parts that have been uploaded.	204

Managing Pre-authenticated Requests

Pre-authenticated requests provide a way to let users access a bucket or an object without having their own credentials.

Request	Append to Path <i>/n/namespaceName</i>	Description	Normal Response Code
POST	<i>/b/bucketName/p/</i>	(CreatePreauthenticatedRequest) Creates a pre-authenticated request specific to the bucket.	200
DELETE	<i>/b/bucketName/p/parID</i>	(DeletePreauthenticatedRequest) Deletes the specified pre-authenticated request.	200
GET	<i>/b/bucketName/p/parID</i>	(GetPreauthenticatedRequest) Gets the specified pre-authenticated request.	200
GET	<i>/b/bucketName/p/</i>	(ListPreauthenticatedRequests) Lists pre-authenticated requests for the bucket.	200

Managing Retention Rules

A retention rule specifies the length of time to retain data in a bucket.

Request	Append to Path <i>/n/namespaceName</i>	Description	Normal Response Code
POST	<i>/b/bucketName/retentionRules</i>	(CreateRetentionRule) Creates a new retention rule in the specified bucket.	200
DELETE	<i>/b/bucketName/retentionRules/retentionRuleId</i>	(DeleteRetentionRule) Deletes the specified rule.	204
GET	<i>/b/bucketName/retentionRules/retentionRuleId</i>	(GetRetentionRule) Get the specified retention rule.	200
GET	<i>/b/bucketName/retentionRules</i>	(ListRetentionRules) List the retention rules for the specified bucket.	200
PUT	<i>/b/bucketName/retentionRules/retentionRuleId</i>	(UpdateRetentionRule) Update the specified retention rule.	200

