

HYPERION® SYSTEM™ 9 BI+
ANALYTIC SERVICES

RELEASE 9.2

ANALYTIC SQL INTERFACE GUIDE



Copyright 1998–2006 Hyperion Solutions Corporation.
All rights reserved.

“Hyperion,” the Hyperion “H” logo, and Hyperion’s product names are trademarks of Hyperion. References to other companies and their products use trademarks owned by the respective companies and are for reference purpose only.

No portion of this manual may be reproduced or transmitted in any form or by any means, electronic or mechanical, including photocopying, recording, or information storage and retrieval systems, for any purpose other than the purchaser’s personal use, without the express written permission of Hyperion Solutions Corporation.

The information contained in this document is subject to change without notice. Hyperion shall not be liable for errors contained herein or consequential damages in connection with the furnishing, performance, or use of this material.

The software described in this document is licensed exclusively subject to the conditions set forth in the Hyperion license agreement. Please read and agree to all terms before using this software.

GOVERNMENT RIGHTS LEGEND: Use, duplication or disclosure by the U.S. Government is subject to restrictions set forth in the applicable Hyperion license agreement and as provided in DFARS 227.7202-1(a) and 227.7202-3(a) (1995), DFARS 252.227-7013(c)(1)(ii) (Oct 1988), FAR 12.212(a) (1995), FAR 52.227-19, or FAR 52.227-14, as applicable.

Hyperion Solutions Corporation
5450 Great America Parkway
Santa Clara, CA 95054

Printed in the U.S.A.

Contents

Purpose	vi
Audience	vi
Document Structure	vi
Where to Find Documentation	vi
Conventions	vii
Additional Support	viii
Education Services	viii
Consulting Services	viii
Technical Support	viii
Documentation Feedback	ix
CHAPTER 1 Introducing	
Analytic SQL Interface	11
New Features	12
New for Release 9.0	12
Understanding SQL Interface	12
Preparing for Data Loading	13
CHAPTER 2 Configuring a Data Source	15
Configuring a Data Source on Windows	16
Example: Configuring a Data Source on Windows 2000	16
Configuring a Data Source on UNIX	16
Understanding the .odbc.ini File	17
Editing the .odbc.ini File for Changes	17
Example: Editing .odbc.ini for DB2	17
CHAPTER 3 Preparing Multiple-Table Data for Loading	19
Understanding Multiple-Table Preparation	20
Understanding Two Methods for Multiple-Table Data Preparation	20
Choosing a Preparation Method	21
Understanding Security Requirements	21
Preparing Data from Multiple Tables	22

CHAPTER 4 Loading SQL Data	23
Understanding Data Loading	24
Using Substitution Variables	24
Understanding the Rules for Substitution Variables	24
Creating and Using Substitution Variables	24
Loading Relational Data Using SQL Interface	25
Summary of Steps	25
Creating the Data Load Rules File	25
Selecting the SQL Data Source	25
Creating SQL Queries (optional)	26
Loading the Data	26
CHAPTER 5 Using Non-DataDirect ODBC Drivers	29
Configuring a Non-DataDirect Driver	30
Creating a Configuration File for Non-DataDirect Drivers	30
Including the Minimum Required Contents	30
Finding a Driver Name on Windows	32
Finding a Driver Name on UNIX	33
Example: Creating a Configuration File for the MS Access Driver on Windows	33
Example: Creating a Configuration File for the IBM DB2 Driver on AIX	33
Configuring Non-DataDirect Data Sources	34
Support for Non-DataDirect Drivers	34
Index	35

Preface

Welcome to the *Analytic SQL Interface Guide*. This preface discusses the following topics:

- “Purpose” on page vi
- “Audience” on page vi
- “Document Structure” on page vi
- “Where to Find Documentation” on page vi
- “Conventions” on page vii
- “Additional Support” on page viii
- “Documentation Feedback” on page ix

Purpose

Use this guide to help you load data from SQL, relational, and flat-file data sources into an Analytic Services database. It explains the SQL Interface features and options and contains the concepts, processes, procedures, formats, tasks, and examples that you need to use the software.

Audience

This guide is primarily for database administrators who install SQL Interface, configure Open Database Connectivity (ODBC) drivers, and load relational data into Analytic Services databases.

To use the information in this book, you need an understanding of relational databases and ODBC drivers, and knowledge of Analytic Services database outlines.

Document Structure

This document contains the following information:

[Chapter 1, “Introducing Analytic SQL Interface,”](#) provides a high-level list of steps for using SQL Interface.

[Chapter 2, “Configuring a Data Source,”](#) provides information and instructions to select and configure the correct database driver to ensure a fast and smooth data load.

[Chapter 3, “Preparing Multiple-Table Data for Loading,”](#) provides instructions to prepare data for loading into an Analytic Services database.

[Chapter 4, “Loading SQL Data,”](#) provides information and instructions to construct a data load rules file to map the data source to the Analytic Services database.

[Chapter 5, “Using Non-DataDirect ODBC Drivers,”](#) provides information you can use if you need to use ODBC drivers other than those supplied by Analytic Services

The [Index](#) contains a list of Hyperion SQL Interface terms and their page references.

Where to Find Documentation

All Analytic Services documentation is available from the following locations:

- The HTML Information Map is located at `installation_directory\docs\esb_infomap.htm`, where *installation_directory* is the directory in which you have installed the Analytic Services documentation.
- Online help is available from within Analytic Administration Services Console. After you log on to the console, you can access online help by clicking the Help button or selecting Help from the menu bar.
- The Hyperion Solutions Web site is located at <http://www.hyperion.com>.

- The Hyperion Download Center can be accessed from <http://hyperion.subscribenet.com> or from <http://www.hyperion.com>.

➤ To access documentation from the Hyperion Download Center:

- 1 Go to the Hyperion Solutions Web site and navigate to **Services > WorldWide Support > Download Center**.

Note: Your Login ID for the Hyperion Download Center is your e-mail address. The Login ID and Password required for the Hyperion Download Center are different from the Login ID and Password required for Hyperion Support Online through Hyperion.com. If you are not sure whether you have a Hyperion Download Center account, follow the on-screen instructions.

- 2 In the **Login ID** and **Password** text boxes, enter your e-mail address and password.

- 3 In the **Language** list box, select the appropriate language and click **Login**.

- 4 If you are a member on multiple Hyperion Solutions Download Center accounts, select the account that you want to use for the current session.

- 5 To access documentation online, from the Product List, select the appropriate product and follow the on-screen instructions.

Conventions

The following table shows the conventions that are used in this document:

Table i Conventions Used in This Document

Item	Meaning
➤	Arrows indicate the beginning of procedures consisting of sequential steps or one-step procedures.
Brackets []	In examples, brackets indicate that the enclosed elements are optional.
Bold	Bold in procedural steps highlights major interface elements.
CAPITAL LETTERS	Capital letters denote commands and various IDs. (Example: CLEARBLOCK command)
Ctrl + 0	Keystroke combinations shown with the plus sign (+) indicate that you should press the first key and hold it while you press the next key. Do not type the plus sign.
Ctrl+Q, Shift+Q	For consecutive keystroke combinations, a comma indicates that you press the combinations consecutively.
Example text	Courier font indicates that the example text is code or syntax.
<i>Courier italics</i>	Courier italic text indicates a variable field in command syntax. Substitute a value in place of the variable shown in Courier italics.
<i>ARBORPATH</i>	When you see the environment variable <i>ARBORPATH</i> in italics, substitute the value of ARBORPATH from your site.

Table i Conventions Used in This Document (*Continued*)

Item	Meaning
<i>HYPERION_HOME</i>	The environment variable <i>HYPERION_HOME</i> stands for the location of the <i>hyperion\common</i> folder on Windows systems. The common folder is where common files used by Analytic Services and other Hyperion products.
<i>n, x</i>	Italic <i>n</i> stands for a variable number; italic <i>x</i> can stand for a variable number or an alphabet. These variables are sometimes found in formulas.
Ellipses (...)	Ellipsis points indicate that text has been omitted from an example.
Mouse orientation	This document provides examples and procedures using a right-handed mouse. If you use a left-handed mouse, adjust the procedures accordingly.
Menu options	Options in menus are shown in the following format. Substitute the appropriate option names in the placeholders, as indicated. <i>Menu name > Menu command > Extended menu command</i> For example: 1. Select File > Desktop > Accounts .

Additional Support

In addition to providing documentation and online help, Hyperion offers the following product information and support. For details on education, consulting, or support options, click the Services link at the Hyperion Solutions Web site.

Education Services

Hyperion offers instructor-led training, custom training, and e-Learning covering all Hyperion applications and technologies. Training is geared to administrators, end users, and information systems professionals.

Consulting Services

Experienced Hyperion consultants and partners implement software solutions tailored to clients' particular reporting, analysis, modeling, and planning requirements. Hyperion also offers specialized consulting packages, technical assessments, and integration solutions.

Technical Support

Hyperion provides enhanced electronic-based and telephone support to clients to resolve product issues quickly and accurately. This support is available for all Hyperion products at no additional cost to clients with current maintenance agreements.

Documentation Feedback

Hyperion strives to provide complete and accurate documentation. Your opinion on the documentation is of value, so please send your comments by going to http://www.hyperion.com/services/support_programs/doc_survey/index.cfm.



Introducing Analytic SQL Interface

Use this chapter to learn about Analytic SQL Interface and prepare for loading data with it:

In This Chapter	Understanding SQL Interface	12.
	Preparing for Data Loading	13.

New Features

Use this section to identify new features or changes since Release 9.0:

- [“New for Release 9.0” on page 12](#)

New for Release 9.0

Release 9.0 enables you to define a substitution variable for the data source name (DSN) and specify in the rules file the substitution variable name. This feature enables you to use the same rules file for different data sources.

Understanding SQL Interface

SQL Interface is installed automatically with every Analytic Server installation. To use SQL Interface, however, your license file must be enabled for it. Use SQL Interface to load data directly from a number of popular SQL, relational, and flat-file database servers. SQL Interface provides the connection you need to accomplish the following tasks:

- You can execute SQL statements on data before loading. For example, using SQL statements to specify the data to retrieve enables you to load summary data instead of the entire contents of the source database.
- Optionally, you can build dimensions in outlines dynamically as you load data.
- You can load data from flat files that are in text format, as well as connecting directly to the relational source database.

Note: You can load data from spreadsheets or text files using Administration Services without the use of SQL Interface. See the *Administration Services Online Help*.

SQL Interface works with Analytic Administration Services to retrieve data, as follows:

1. You write a SELECT statement in SQL using Administration Services.
2. SQL Interface passes it to the SQL or relational database server. For non-SQL data sources, SQL Interface converts SQL statements to requests for data that the source understands.
3. SQL Interface interprets the records received from the SQL, relational, or flat-file database server using the rules defined in the data load rules file. (For more information on data load rules files, see [Chapter 4, “Loading SQL Data.”](#))
4. SQL Interface loads the interpreted, summary-level data into the database.

Preparing for Data Loading

- ▶ To prepare to load SQL, relational, or flat-file data, use this procedure:
 - 1 SQL Interface is installed during the Analytic Server installation. See the *Analytic Services Installation Guide* for information about initial configuration tasks.
 - 2 Configure the ODBC driver and point it to its data source. See [Chapter 2, “Configuring a Data Source.”](#)
 - 3 If data is in multiple tables, prepare the data for loading by doing either of these actions:
 - Create one table or view in the SQL database before using SQL Interface.
 - Join the tables during the data load by entering a SELECT statement in Administration Services.See [“Understanding Multiple-Table Preparation”](#) on page 20 for instructions.
 - 4 Check that you can connect to the data source by using the Data Prep Editor in Administration Services Console to open the SQL source file. See [Chapter 4, “Loading SQL Data.”](#)
 - 5 Create a data load rules file to tell SQL Interface how to interpret and load the SQL data into the Analytic Services database. See [Chapter 4, “Loading SQL Data.”](#)

After these steps are complete, you can load data. See [Chapter 4, “Loading SQL Data”](#) for instructions.

2

Configuring a Data Source

Before you can access data using Analytic SQL Interface, you must configure the operating system for each data source and the driver it requires. The Analytic Services installation provides DataDirect ODBC drivers.

This chapter describes the procedures for configuring Windows and UNIX. For information about configuring non-DataDirect ODBC drivers, see [Chapter 5, “Using Non-DataDirect ODBC Drivers.”](#) For a complete list of supported ODBC drivers, see *Analytic Services Installation Guide*.

In This Chapter	Configuring a Data Source on Windows	16
	Example: Configuring a Data Source on Windows 2000	16
	Configuring a Data Source on UNIX	16

Note: For detailed, driver-specific information on each of the DataDirect drivers, see the DataDirect Connect for ODBC Reference in the `hyperion\common\odbc\merant\4.2\docs\odbceref\` directory of the Analytic Services installation on Windows, or `hyperion\common\ODBC\Merant\4.2\` on UNIX.

Configuring a Data Source on Windows

On Windows, use the ODBC Administrator to configure the data source.

- To configure the ODBC Administrator, complete the following steps:
 - 1 Start the ODBC Administrator by opening the Windows Control Panel and double-clicking the **Administrative Tools** icon, and then double-clicking the **Data Sources** icon.
 - 2 Choose a data source, or add one, and then enter the required information about the driver.

For detailed instructions, see the documentation from the ODBC provider.

Example: Configuring a Data Source on Windows 2000

- To configure the SQL Server data source, complete the following steps:
 - 1 Start the ODBC Administrator, using the instructions in [Step 1](#) in “[Configuring a Data Source on Windows](#)” on page 16.
 - 2 Click the **System DSN** tab in the ODBC Data Source Administrator dialog box:
 - 3 Click **Add** on the System DSN tab. The Create New Data Source dialog box is displayed.
 - 4 From the list box, select **SQL Server** and click the **Finish** button to display the General tab of the Create a New Data Source to SQL Server dialog box.
 - 5 Type the following information in the Create a New Data Source to SQL Server dialog box:
 - a. In the Name text box, type TBC.
 - b. In the Description text box, type Load Files.
 - c. In the Server text box, type the name of the server computer to which you are connecting. If the data source resides on your local computer, type your computer name.
 - d. Click OK.

The System DSN tab of the ODBC Data Source Administrator dialog box is displayed with TBC listed in the System Data Sources list box.

- 6 Click **OK** to close the **ODBC Data Source Administrator**.

For help with this procedure, access the ODBC Data Source Administrator online help by clicking the **Help** button.

Configuring a Data Source on UNIX

After installing Analytic Services, you must execute the `inst-sql.sh` file to enable SQL Interface.

The `inst-sql.sh` setup script copies the file `$HYPERION_HOME/ODBC/Merant/4.2/odbc.ini` into `$ARBPORPATH/bin/.odbc.ini`, and creates the link `.odbc.ini` in the user home directory.

Note: SQL Interface must be enabled in the Analytic Services registration number before it can be used.

To run Hybrid Analysis on UNIX platforms, set, in the `.profile`, the `ODBCINI` environment variable to `$ARBORPATH/bin/.odbc.ini`, which contains the definition for the relational data source.

If you add data sources or drivers, you may need to edit the `.odbc.ini` file:

- [“Understanding the .odbc.ini File” on page 17](#)
- [“Editing the .odbc.ini File for Changes” on page 17](#)
- [“Example: Editing .odbc.ini for DB2” on page 17](#)

Understanding the .odbc.ini File

The `.odbc.ini` file contains the ODBC connection and configuration information, such as data source name and driver product name. Specific information varies among platforms. The file and format are defined by the Microsoft ODBC specification.

Editing the .odbc.ini File for Changes

Because the `.odbc.ini` file maps data source names to driver products, you must edit the `.odbc.ini` file if you add a new driver product or data source or change driver products or data sources.

Example: Editing .odbc.ini for DB2

The following example illustrates how you might edit the `.odbc.ini` file on an Analytic Server running on AIX, to connect to a DB2 8.1 database named “`tbc_data`,” using an ODBC data source named `db2data` that invokes the DataDirect 4.2 Wire Protocol driver.

Use the `vi $ODBCINI` command to edit the `.odbc.ini` file and insert the following statements:

```
[ODBC Data Sources]
db2data=DB2 Source Data on AIX

...

[db2data]
Driver=/home/hyperion/essbase/odbc/merant42/lib/ARdb218.so
IpAddress=isaix7
Database=tbc_data
TcpPort=xxxxx
Package=PACK4A
Action=REPLACE
QueryBlockSize=8
CharSubType=SYSTEM_DEFAULT
ConversationType=SINGLE_BYTE
CloseConversation=DEALLOC
```

```
UserBufferSize=32
MaximumClients=35
GrantExecute=1
GrantAuthid=PUBLIC
OEMANSI=1
DecimalDelimiter=PERIOD
DecimalPrecision=15
StringDelimiter=SINGLE_QUOTE
IsolationLevel=CURSOR_STABILITY
ResourceRelease=DEALLOCATION
DynamicSections=32
Trace=0
WithHold=0
```

The following example illustrates how you might edit `.odbc.ini` to connect to a Data Source database, such as “db2data” on DB2 Version 8.1 (on AIX), using an IBM DB2 ODBC driver.

Use the `vi $ODBCINI` command to edit the `.odbc.ini` file and insert the following statements:

```
[ODBC Data Sources]
db2data=DB2 Source Data on AIX
...

[db2data]
Driver=/home/db2inst1/sqlllib/lib/db2_36.o
Description=DB2 Data Source - AIX, native
```



Preparing Multiple-Table Data for Loading

This chapter describes how to prepare relational data in multiple tables for loading into Analytic Services:

In This Chapter	Understanding Multiple-Table Preparation	20
	Preparing Data from Multiple Tables	22

Understanding Multiple-Table Preparation


Use this section to understand the two methods available for preparing multi-table data:

- [“Understanding Two Methods for Multiple-Table Data Preparation”](#) on page 20
- [“Understanding Security Requirements”](#) on page 21
- [“Choosing a Preparation Method”](#) on page 21

Understanding Two Methods for Multiple-Table Data Preparation


If data is in multiple tables, create a single table or a view of the data in either of the following ways:

- Create one table or view in the SQL database before using SQL Interface:



See [“Choosing a Preparation Method”](#) on page 21 for instructions.

- Join the tables by entering a SELECT statement in Administration Services Console during the data load:



See [“Preparing Data from Multiple Tables” on page 22](#) for instructions.

Choosing a Preparation Method

A SQL database server reads from a single table and maintains a single view more efficiently than it processes a multiple-table SELECT statement. Therefore, creating a single table or view before you use SQL Interface greatly reduces the amount of processing time the SQL server needs.

Understanding Security Requirements

Data load preparation requires specific permissions:

- For any data load preparation method, you need SELECT access privileges to all tables containing the relevant data.
- For creating a single table or view in the relational database source, you need CREATE access privileges in the SQL database to create a single table or view. Ask the SQL Database Administrator to provide you with the appropriate CREATE privileges.

If you cannot obtain CREATE privileges, use Administration Services to join tables during the data load. See [“Preparing Data from Multiple Tables” on page 22](#) for instructions.

Preparing Data from Multiple Tables

► Use this process to prepare data from multiple tables:

1 Obtain the required privileges:

- SELECT access to all tables where relevant data is stored
- CREATE access to create a single table or view to join multiple-table data before using SQL Interface

2 Use one of these methods to prepare data from multiple tables:

- Create a single physical table or virtual table (view) based on data from multiple tables in the source database.
- Create a SELECT statement in Administration Services Console that joins the tables:
 - i. Identify the tables and columns (or fields) containing the data that you want to load into Analytic Services.
 - ii. Select **File > Open SQL** in the Administration Services Console to display the **Open SQL Data Sources** dialog box.

For detailed information, see “Opening an SQL Database” in *Administration Services Online Help*.

- iii. Write a SELECT statement that joins the tables.

For more information, see “[Selecting the SQL Data Source](#)” on page 25 and “[Creating SQL Queries \(optional\)](#)” on page 26.

Note: Analytic Services passes the SELECT statement to SQL Server without verifying the syntax.

4

Loading SQL Data

This chapter describes how to load SQL data into Analytic Server using Analytic Administration Services:

In This Chapter	Understanding Data Loading	24
	Using Substitution Variables.	24
	Loading Relational Data Using SQL Interface	25
	Loading the Data.	26

Examples in this section are based on samples provided with the installation:

- The Sample application
- The Basic database

Understanding Data Loading

After you have configured the data source and prepared the multiple-table data for loading, load the data.

- To load the data:
 - 1 If you plan to use substitution variables, create them. See [“Using Substitution Variables” on page 24](#) for instructions.
 - 2 Create a rules file. See [“Loading Relational Data Using SQL Interface” on page 25](#).
 - 3 Load data into the Analytic Services database. See [“Loading the Data” on page 26](#).

Using Substitution Variables

Similar to report scripts and calculation scripts, you can use substitution variables in SQL strings and data source names. You can use substitution variables that apply to all applications and databases on Analytic Server, or specify them for a particular application or database.

Understand the rules for substitution variable use in Analytic SQL Interface before you create and use them:

- [“Understanding the Rules for Substitution Variables” on page 24](#)
- [“Creating and Using Substitution Variables” on page 24](#)

Understanding the Rules for Substitution Variables

Remember these rules when you create substitution variables:

- The value of the substitution variable should be valid and appropriate SQL. Analytic Services does not validate the value.
- Be especially careful when you use quotation marks or single quotes. Different source databases have different conventions about when to use them.
- Whether or not you use a substitution variable, be sure that no regular SQL operators in SELECT, FROM, or WHERE clauses start with the ampersand (&), because that is the Analytic Services identifier for substitution variables.

Creating and Using Substitution Variables

- To create and use a substitution variable, use the following procedure:
 - 1 Create the substitution variable using the instructions in [“Managing Substitution Variables” in Administration Services Online Help](#).
 - 2 To open the SQL data source when you edit the rules file select **File > Open SQL** from the menu. See [“Creating a Rules File” in Administration Services Online Help](#). Specify substitution variables in the resulting **Open SQL Data Sources** dialog box.

- To specify a substitution variable for the DSN, select **Substitution Variables** and select the substitution variable from the list.
 - To specify substitution variables in the query, use the substitution variable instead of a “field=value” string in the **Select**, **From**, or **Where** box. Remember to type the ampersand (&) in front of the substitution variable name.
- 3** Click **OK/Retrieve** to retrieve the data for the rules file.

Note: Be sure to set the desired value for the substitution variables before you use the rules file for a data load or dimension build.

Loading Relational Data Using SQL Interface

To load SQL data into the Analytic Services database, you must create and use a data load rules file.

Data load rules are a set of operations that Analytic Services performs on data when it loads it into an Analytic Services database. The operations are stored in a rules file that tells Analytic Services how to load the data and map it to your database outline. The rules file can also reject invalid records in the data source.

Summary of Steps

1. Create a data load rules file.
2. Select your SQL data source. See [“Selecting the SQL Data Source” on page 25](#) for instructions.
3. If you plan to create SQL queries in Analytic Services, see [“Creating SQL Queries \(optional\)” on page 26](#).

Creating the Data Load Rules File

- To create a data load rules file, use the instructions in *Creating a Data Load Rules File* in *Administration Services Online Help*.

Selecting the SQL Data Source

When you create a rules file you must specify a data source.

- To select a SQL data source:
 - 1** In **Administration Services Console**, open **Data Prep Editor** or an existing rules file.
 - 2** Choose **File > Open SQL**.
 - 3** In the **Select Database** dialog box, enter the Analytic Server, application, and database. and click **OK**.

- 4 In the **Open SQL Data Sources** dialog box, select the data source and enter required information. See “Opening an SQL Database” in *Administration Services Online Help* for detailed instructions.
- 5 Click **OK/Retrieve**.
- 6 In the **SQL Connect** dialog box, enter the user name and password for the source database and click **OK**.

Note the following facts about data source files:

- The data source file must be stored on the server computer.
- On UNIX platforms, if you have defined the path for the SQL data source file in the `.odbc.ini` file, you can either enter that path or a different path in the Database text box of the Define SQL dialog box.
- On Windows, if you have not defined the path for the SQL source file in the ODBC Administrator, you can type the path in the Database text box of the Define SQL dialog box.
- If you do not define a path, Analytic Services looks for the data source file in the directory from which you are running Analytic Server.

Creating SQL Queries (optional)

If you have not created a table or view to retrieve only the information you need from the data source, you can write a SELECT statement to achieve this goal.

Note: Creating a SELECT statement in Analytic Services is usually slower than creating a table or view in the source database.

The SQL Statement text box in the Open SQL Data Sources dialog box has Select, From, and Where text boxes to help you write SQL queries. You can specify multiple data sources, filter the display of records, and specify the desired order and grouping of records that will appear in the Data Prep Editor.

Loading the Data

- To load SQL data into the Analytic Services database:
 - 1 In the Administration Services Console, select the database.
 - 2 Right-click and select **Load Data** from the pop-up menu.
 - 3 In the **Data Load** dialog box, in the **Type** option group, select **SQL**.
 - 4 Select the **Use rules** check box and click **Find**.
 - 5 In the **Open Rules File** dialog box, browse for the rules file.
 - 6 Select the rules file and click **OK**.
 - 7 In the **Options** group, select the **Load data** option.

For a description of the other options, click **Help**.

8 Click **OK** to load the data.

Note: After loading data using SQL Interface, connections to the relational data source may remain open.

5

Using Non-DataDirect ODBC Drivers

You can use drivers other than the DataDirect drivers provided with Analytic Services. For example, you can use a Microsoft ODBC driver to connect to Microsoft Access. Some non-DataDirect ODBC drivers are tested with Analytic Services. For detailed information on tested and supported drivers and data sources, see the *Analytic Services Installation Guide*.

- ▶ To use a non-DataDirect driver, you need to:
 - 1 **Configure the driver for all drivers and data sources.**
 - 2 **Configure the data source if you are using Teradata.**

This chapter contains the following topics that describe how to use non-DataDirect ODBC drivers:

In This Chapter	Configuring a Non-DataDirect Driver	30
	Creating a Configuration File for Non-DataDirect Drivers	30
	Configuring Non-DataDirect Data Sources	34
	Support for Non-DataDirect Drivers	34

Configuring a Non-DataDirect Driver

When you configure a DataDirect driver, Analytic Services recognizes the basic configuration information for the driver, especially the name of the driver and whether the name and password are case-sensitive. However, when you use a non-DataDirect driver, you must give Analytic Services the configuration information for the driver that you use.

You give Analytic Services the configuration information for your non-DataDirect driver by creating a driver configuration file called `esssql.cfg`, which is a text file. Place this file in your `ARBORPATH\BIN` directory on Analytic Server. This is `c:\hyperion\essbase\` if you installed Analytic Services in the default directory (`/home/hyperion/essbase/` on UNIX platforms).

Note: If you do not create a configuration file, Analytic Services uses its own default values. You may not be able to connect to the SQL database using the default values.

Creating a Configuration File for Non-DataDirect Drivers

For non-DataDirect drivers, you create a configuration file: `$ARBORPATH/bin/esssql.cfg`. The configuration file must contain at least some of the following configuration values for each non-DataDirect ODBC driver that you use. Required values may be different for different drivers. See the online help for each driver or see the documentation for specific information.

This section contains information about what you need to include in the configuration file, and in one case, how to find it:

- [“Including the Minimum Required Contents” on page 30](#)
- [“Finding a Driver Name on Windows” on page 32](#)
- [“Finding a Driver Name on UNIX” on page 33](#)
- [“Example: Creating a Configuration File for the MS Access Driver on Windows” on page 33](#)
- [“Example: Creating a Configuration File for the IBM DB2 Driver on AIX” on page 33](#)

Including the Minimum Required Contents

At a minimum, the configuration file must contain at least the *DriverName* for every non-DataDirect ODBC driver that you use. Surround all values for each driver with brackets (`[]`). Leave one or more spaces between the configuration keyword and its corresponding value.

Use this template to help you create a configuration file:

```
[
Description                "Description of Driver"
DriverName                  DriverName
UserId                      Value
```

Password *Value*
 Database *Value*
 Server *Value*
 Application *Value*
 Dictionary *Value*
 Files *Value*
 SingleConnection *Value*
 UpperCaseConnection *Value*
 IsQEDriver *Value*
]

Description of Driver is your description of the driver. Enclose the description in quotation marks (""). The default value is "".

DriverName is the file name of the non-DataDirect ODBC driver and is required.

For all other configuration keywords, set *Value* to be either 1 or 0, according to the following table:

Configuration Information	Value	Description
UserId	1	User ID required.
	0	User ID not required. Default: 0
Password	1	Password required.
	0	Password not required. Default: 0
Database	1	Database name required.
	0	Database name not required. Default: 0
Server	1	Server name required.
	0	Server name not required. Default: 0
Application	1	Application name required.
	0	Application name not required. Default: 0
Dictionary	1	Dictionary name required.
	0	Dictionary name not required. Default: 0
Files	1	Files name required.
	0	Files name not required. Default: 0

Configuration Information	Value	Description
SingleConnection	1	Driver not thread-safe. One active connection allowed. Default: 1 Recommendation for DataDirect drivers: 1
	0	Driver thread-safe. Multiple active connections allowed. CAUTION! Specifying 0 (multiple active connections allowed) for DataDirect or non-DataDirect drivers may lead to instability.
UpperCaseConnection	1	Driver not case-sensitive. Connection information is converted to uppercase.
	0	Driver case-sensitive. Connection information is unchanged. Default: 0
IsQEDriver	1	Driver is a DataDirect driver. You can specify configuration information for DataDirect drivers (for example, if you have a later version of a DataDirect driver which Analytic Services does not yet support).
	0	Driver is a non-DataDirect driver. Default: 0

The defaults apply if you do not specify the value for the driver. These defaults are different from the Analytic Services default values that apply if you do not create an `esssql.cfg` file.

Include configuration information for all the non-DataDirect drivers in one configuration file. Enclose the values for each driver in brackets ([]).

Use this template to help you create a configuration file:

```
[
Description          "Description of Driver"
DriverName           DriverName
...
]
```

```
[
Description          "Description of Driver"
DriverName           DriverName
...
]
```

Finding a Driver Name on Windows

► To display the name of the drive, use this procedure:

- 1 Start the ODBC Administrator using any method from [Step 1](#) in “Configuring a Data Source on Windows” on [page 16](#).

The ODBC Data Source Administrator dialog box appears.

Data sources that you have configured are in the **User Data Sources** list box. Drivers that have not been properly configured may also appear in the User Data Sources list box. Ignore them.

- 2 Select the **Drivers** tab.
- 3 Obtain the file name of the driver by scrolling to the right. For example, the file name for the **Microsoft Access Driver** is `ODBCJT32.DLL`.
- 4 Select the driver, and click **OK**.

Finding a Driver Name on UNIX

On UNIX, the driver name is in the `.odbc.ini` file. For more information on the `.odbc.ini` file, see [“Configuring a Data Source on UNIX” on page 16](#).

Example: Creating a Configuration File for the MS Access Driver on Windows

The driver name for the Microsoft Access driver on Windows is `ODBCJT32.DLL`. This driver requires a database name, server name, application name, and dictionary (directory path). This driver is not a DataDirect driver, so you must create a configuration file, `$ARBORPATH/bin/esssql.cfg` in text format.

Use this example as a template:

```
[
Description                "Microsoft Access Driver (*.MDB)"
DriverName                  ODBCJT32.DLL
Database                    1
Server                      1
Database                    1
Application                 1
Dictionary                  1
IsQEDriver                  0
]
```

Example: Creating a Configuration File for the IBM DB2 Driver on AIX

The driver name for the IBM DB2/6000 driver on AIX is `DB2.0`. This driver requires a user ID, password, and database name, but not a server name. This driver is thread-safe and case-sensitive. It is not a DataDirect driver, so you must create a configuration file, `$ARBORPATH/bin/esssql.cfg`, in text format.

Use this example as a template:

```
[
Description                "IBM DB2/6000 ODBC Driver"
DriverName                  DB2.0
UserId                      1
Password                    1
Database                    1
SingleConnection            0
UpperCaseConnection         0
IsQEDriver                  0
]
```

Configuring Non-DataDirect Data Sources

The procedure for configuring non-DataDirect data sources is similar to that for configuring DataDirect data sources. See [Chapter 2, “Configuring a Data Source”](#) for detailed information. For specific instructions on configuring a non-DataDirect data source, please reference your ODBC documentation.

Note: Before you configure a non-DataDirect data source, you must first configure the driver by creating an `esssql.cfg` configuration file. See [“Creating a Configuration File for Non-DataDirect Drivers”](#) on page 30.

Support for Non-DataDirect Drivers

Some non-DataDirect drivers are not tested or supported for use with Analytic Services. The driver that you choose might not be specifically tested to work with Analytic Services. For information on qualified drivers and data sources, see the *Analytic Services Installation Guide*.

Index

A

Administration Services

- joining tables, [20](#)
- loading spreadsheet data, [12](#)
- loading SQL data, [23](#)
- SELECT statement, [20](#), [22](#)

AIX environments, IBM DB2/6000

- driver, [33](#)

Analytic Services

- default values for drivers, [30](#) to [31](#)
- loading data into, [vi](#)
- outline, mapping data to, [25](#)

Analytic Services, loading data into, [23](#)

ARBORPATH, [30](#)

audience for this guide, [vi](#)

B

BIN directory, [30](#)

building Analytic Services dimensions, [12](#)

C

cfg (.CFG) file, creating, [30](#)

choosing, a driver, [16](#)

configuration file, for non-MERANT drivers, [30](#)

configuring

- data sources
 - non-MERANT, [34](#)
 - overview, [15](#)
- Microsoft Access ODBC driver, [33](#)
- non-MERANT drivers, [30](#), [32](#)

consulting services, [viii](#)

converting SQL statements, [12](#)

CREATE privileges, [21](#)

creating

data load rules file, [25](#)

driver configuration file, [30](#) to [31](#)

Microsoft Access driver configuration file, [33](#)

security privileges for single table or view, [21](#)

single table or view, [20](#) to [21](#)

D

data

- load preparation, [19](#)
- load preparation methods, [21](#)
- SQL, mapping, [25](#)

data load rules file

- creating, [25](#)
- definition, [25](#)
- SQL records, [12](#)

data sources

- non-MERANT, [34](#)
- paths, [26](#)
- selecting, [25](#)

databases

- multidimensional, [vi](#)
- multidimensional data, summary level, [12](#)

DB2

- odbc.ini file example, [17](#) to [18](#)

DB2.0, [33](#)

dialog boxes

- Create New Data Source, [16](#)
- Data Load, [26](#)
- Define SQL, [21](#)
- ODBC Data Source Administrator, [16](#), [33](#)

dimensions, building, [12](#)

directories

- BIN, [30](#)
- data sources, default, [26](#)

- driver configuration file, [30](#)
- documents
 - conventions used, [vii](#)
 - feedback, [ix](#)
 - structure of, [vi](#)
- documents, accessing
 - Hyperion Download Center, [vii](#)
- driver configuration file
 - creating, [30 to 31](#)
 - for Microsoft Access, [33](#)
 - default values, [30 to 31](#)
 - in BIN directory, [30](#)
 - keyword values, [31](#)
 - required values, [30](#)
 - syntax, non-MERANT drivers, [32](#)
- drivers
 - choosing in ODBC Administrator, [16](#)
 - configuring
 - for IBM DB2/6000, [33](#)
 - non-MERANT, [34](#)
 - description of, [31](#)
 - file names, [33](#)
 - naming, [31](#)
 - non-DataDirect, [29](#)
 - non-MERANT, [34](#)
 - password, [30](#)
 - UNIX, names, [33](#)

E

- education services, [viii](#)
- esssql.cfg, [30 to 34](#)
- examples, odbc.ini files, [17 to 18](#)

F

- files, .CFG (configuration), [30](#)
- flat file data, loading, [vi](#)

H

- Hyperion Consulting Services, [viii](#)
- Hyperion Download Center
 - accessing documents, [vii](#)
- Hyperion Education Services, [viii](#)
- Hyperion product information, [viii](#)
- Hyperion Technical Support, [viii](#)

I

- IBM DB2/6000
 - data source, ODBC driver for, [33](#)
- installed ODBC drivers, listed, [33](#)
- interpreting SQL records, [12](#)

J

- joining tables, [20](#)
 - Administration Services, [20](#)
 - SELECT statement, [22](#)

K

- keywords, driver configuration file, [31](#)

L

- loading data, [vi](#)
 - data load rules, [25](#)
 - from single table, [20](#)
 - into outline, [26](#)
 - joining tables, [20, 22](#)
 - overview, [13, 24](#)
 - preparing for, [19](#)
 - summary level data, [12](#)
 - using Administration Services, [23](#)

M

- mapping
 - SQL data to an Analytic Services outline, [25](#)
- Microsoft Access
 - ODBC driver for, [33](#)
- multidimensional databases
 - building Analytic Services dimensions, [12](#)
 - loading data into, [vi, 12](#)
- multiple tables
 - joining, [20, 22](#)
 - loading from, [19](#)
 - preparing, [19](#)

N

- non-DataDirect
 - drivers
 - configuring, [29](#)

non-MERANT

data source, configuring, 34

drivers

tested, 29

drivers tested, 34

O

ODBC Administrator, 16

ODBC drivers

configuring for IBM DB2/6000, 33

file names, 33

non-DataDirect, 29

tested, 29

UNIX, names, 33

odbc.ini file, 26

DB2 example, 17 to 18

ODBCJT32.DLL, 33

outline

loading data, 26

P

passing

SELECT statements, 22

SQL statements, 12

passwords

for driver, 30

for IBM DB2/6000 driver, 33

paths

esssql.cfg, 30

for data sources, 26

prerequisites for using this guide, vi

processing time, 21

R

relational data, loading, 12

See also data

requesting non-SQL data, 12

S

security privileges, 21

SELECT statement, 20, 22

processing time, 21

selecting, 25

SQL data sources, 25

SQL

queries, 26

statements, 12

SQL data

joining tables, 20

loading, vi, 12

mapping, 25

selecting source, 25

SQL databases

single tables in, 20 to 21

SQL server, 21

summary data, loading, 12

T

tables

creating, 20

efficiency, 21

joining, 20, 22

loading from, 19

SQL databases, 20

technical support, viii

tested

drivers, 29

non-MERANT drivers, 34

text file data, loading, 12

U

UNIX environments

IBM DB2/6000 driver, 33

odbc.ini file, 26, 33

V

views, 21

creating, 20

SQL databases, 20

W

Windows NT environments

configuring data sources on, 16

ODBC Administrator, configuring data sources, 16

A B C D E F G H I J K L M N O P Q R S T U V W X Y Z