Oracle® Utilities Work and Asset Management

Business Intelligence Guide Release 1.9.0.4.6 E26186-02

October 2012



Oracle® Utilities Work and Asset Management Business Intelligence User Guide for Release 1.9.0.4.6

Doc v1 rev.0 10/2/12

Copyright ©1986, 2012, Oracle and/or its affiliates. All rights reserved.

Primary Author: TUGBU Documentation

Contributing Author: n/a

Contributor: n/a

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this software or related documentation is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, the following notice is applicable:

U.S. GOVERNMENT RIGHTS

Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, duplication, disclosure, modification, and adaptation shall be subject to the restrictions and license terms set forth in the applicable Government contract, and, to the extent applicable by the terms of the Government contract, the additional rights set forth in FAR 52.227-19, Commercial Computer Software License (December 2007). Oracle America, Inc., 500Oracle Parkway, Redwood City, CA 94065.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications which may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

This software or hardware and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third party content, products and services. Oracle Corporation and its affiliates will not be responsible for any lost, costs, or damages incurred due to your access to or use of third party content, products or services.

Business Intelligence

Oracle Utilities Business Intelligence (BI) for Oracle Utilities Work and Asset Management uses extraction programs packaged with the Oracle Utilities Application Framework (OUAF). The extraction programs for Oracle Utilities Work and Asset Management are written in PL/SQL and are loaded into BI using OUAF.

Users can view batch control records, submit batch jobs and view the batch run tree using the Oracle Utilities Work & Asset Management application.

This section describes the configurations required in Oracle Utilities Work and Asset Management only. For complete Oracle Utilities Business Intelligence implementation and configuration guidelines refer to the online documentation within BI.

Note: It is recommended that you read this entire document before beginning installation.

Certified Version

Certified versions of Business Intelligence include:

- Business Intelligence v2.2.1 and higher for Oracle Utilities Work and Asset Management releases 1.8 and higher.
- Business Intelligence v2.4.0 for Oracle Utilities Work and Asset Management releases 1.9.0.4 and above.

Extract Mapping

Extract mapping information is provided at the end of this document.

Basic Steps to Get Started Multiple Plants Extract Output Batch Procedure Business Rules Sequence Numbering Initial Load and Incremental Load Error Handling File Name Conventions and Outputs SABI Triggers Extracts

Basic Steps to Get Started

- 1. Enable the Oracle Utilities Work and Asset Management BI database triggers using Installation Parameters.
- 2. Setup the BI Batch procedure, SDBP_BI_EXTRACT_HANDLER, in the Job Manager module.
- 3. Configure the OUBI Setup Business Rule.
- 4. Verify sequence numbering for SA_CHANGE_LOG in the Sequence Numbering module.

5. Run the batch procedure, SDBP_BI_EXTRACT_HANDLER.

Multiple Plants

If you have multiple plants all configuration settings must be configured and executed separately for each.

Extract Output

A folder for the extraction file output is required to be created on the database server using the database server operating system. This directory is referred to as the "BI Extract output folder". A database object called a "Directory" needs to be created to point to this folder on the database server file system.

Default

The installation is includes a pre-configured database directory object that is defaulted to "c:\bi_ extract". This serves as a target folder for extracted files. **SD_BI_OUTBOUND** is the directory object in the database that maps to the output directory folder for the BI extracts.

Override the Default

This default can be overridden at the database level by running the following script:

CREATE OR REPLACE DIRECTORY sd_bi_outbound AS '<operating system folder name>' /

Steps to Create the Database Object

- 1. The Directory object must be created by a user with DBA privileges.
- 2. Create the directory object referencing your output folder. To override the default, run the script indicated above.
- 3. Grant privileges to the Directory to the user that will be executing the extract routines. This is the same user that will be creating the objects in the Oracle Utilities Work and Asset Management Job Scheduler.

grant read on directory SD_BI_OUTBOUND to synergen;

grant write on directory SD_BI_OUTBOUND to synergen;

Batch Procedure

The batch procedure, SDBP_BI_EXTRACT_HANDLER, handles and calls all of the extract programs. You can monitor this processing in the Job Manager and the Job Manager Log modules. SDBP_BI_EXTRACT_HANDLER also handles incrementing the value of the sequence number whenever an incremental extract is requested.

Business Rules

OUBI Setup Rule

Desc Th	is rule controls whether an ex	tract is to be done and c	lefines extract details such as	data source	A
ind	licator, file names and output o	irectory.			Ŧ
Comment					
Key Name		Value	Yalue2	Yelus3	
	TRACT PARAMETERS		SD BI OUTBOUND	3	
OUBI EXTRA	CT ASSET	ON	D_ASSET_EXT		
OUBI FISCAL	. PER	ON	D_FISCAL_EXT		
OUBLINV SN	APSHOT	ON	F_STRM_INV_EKT	D	1
OUBI OPER #	ACCT	ON	D_DP_ACCT_EXT		
OUBI OPER #	ACCT TRANS	ON	F_OP_ACTG_EKT		
OUBI OPER #	ACCT TRANS TYPE	ON	D_OP_ACTG_TY_EX		
OUBI OPER B	EXPENSE	ON	D_OP_EXP_EXT		
OUBI OPER L	JOM	ON	D_OP_UOM_EXT		
OUBI STOCK	ITEM	ON	D_STOCK_ITMTY_EX		
OUBI STORE	RM TRANS TYPE	ON	D_STRM_TR_TY_EX		
OUBI STORE	ROOM	ON	D_STRM_EXT		
OUBI STORE	ROOM TRANS	ON	F_STRM_TR_EXT		
Description	ract Parameters				_

Configure settings to determine which extracts will be completed during regular processing. This rule can also be used to define extraction details such as data source, file names and the output directory. If desired, any extract can be turned OFF so that it is not included in the overall extraction.

Common Extract Parameters

The first rule key, COMMON EXTRACT PARAMETERS, defines parameters for all of the extracts that are turned ON. The key values for this rule key differ slightly from the key values for the remaining rule keys.

Value is left blank for this rule key.

Value2 is the name of the directory object in the database. This corresponds to the output folder of the extract, SD_BI_OUTBOUND.

Value3 is the Data Source Indicator. Default value is '3'

Value4 controls which type of extract will be executed. A value of INI means the extract will produce an Initial Extract, an INC means an Incremental Extract. The default value is INI.

After an Initial Extract, the value is automatically updated to INC by SDBP_BI_EXTRACT_ HANDLER so that the succeeding extracts are incremental.

General Key Names and Values

Value controls whether the extract is executed. Default value is ON.

Value2 is the base extract file name. This is the extract identifier used in building the names of the extract files.

Value3 and Value4 only apply to the Key Name OUBI INV SNAPSHOT. The goal of this metric is to compare inventory levels of like stock items based on periodic snapshots of the quantities in the storeroom. This is not a metric used to compare inventory movement because it does not deal with the transaction volume.

This requires two parameters to be passed to the procedures:

Value3 - Type of Increment - Monthly or Daily

Value4 - Number of Historical Snapshots - Any number

Sequence Numbering

Sequence Numbering must be turned on for SA_CHANGE_LOG to control the batch number field of the SA_CHANGE_LOG table. The Oracle Utilities Business Intelligence triggers use the value of this sequence number to uniquely identify records inserted into the SA_CHANGE_LOG table.

Initial Load and Incremental Load

Settings for the OUBI Setup Business Rule COMMON EXTRACT PARAMETERS rule key determine how the data is initially loaded as well as the incremental data loads.

Initial Load

The Initial Load of the extracts will query ALL records from the target tables and sends the entire set of source data to BI. This load is filtered by PLANT. There is no additional filtering applied to the source information. For example, the Account Transactions Extract targets the SA_ACCOUNT_LOG table as the source information. The initial load will take all records in the SA_ACCOUNT_LOG table and send the records to BI.

If you need to extract records from another plant, the batch job, SDBP_BI_EXTRACT_ HANDLER, must be for the other PLANT and executed. Same with the Incremental extracts.

Incremental Load

The Incremental Load is based on information found in the SA_CHANGE_LOG table. Records are inserted into this table from a set of BI extract database triggers placed on various tables in Oracle Utilities Work and Asset Management. The incremental extracts begin to have data in the files after the BI triggers have been enabled in the Oracle Utilities Work and Asset Management database schema. If a record is recorded in the SA_CHANGE_LOG, a transaction is set to BI.

Error Handling

Errors will not occur unless there is a problem with the extracted data or with configuration settings. If errors are encountered, they will be noted in the Job Manager Log module. Correct any errors then re-run an Initial Load.

To Rerun an Initial Load

- 1. Open the OUBI Setup Business Rule.
- 2. Set the Common Extract Parameters rule key to 'INI.'
- 3. Execute the batch job, SDBP_BI_EXTRACT_HANDLER.
 - After an Initial Extract, the business rule value is automatically updated to INC by SDBP_ BI_EXTRACT_HANDLER so that the succeeding extracts are incremental.

File Name Conventions and Outputs

File Names follow the standard naming convention expected by OUBI. The OUBI Setup Business Rule handles the prefix file name for all the extracts. This is the value under the Value2 column. These filenames cannot be modified. The structure is indicated here to provide insight into how information can be determined from the file name.

Example: EXTDASSE000003000000021001.<extension name>

- Extract Identifier: No limit on the size
- Data Source Indicator: Next 6 characters
- Batch Number: Next 10 characters
- Thread Number: Next 3 characters

Each extract produces two files: *.DAT and *.CTL.

- **DAT** files contain the actual extract data from the Oracle Utilities Work and Asset Management tables.
- **CTL** files are used by Oracle Utilities BI for log and upload trace details. The file contains one line of information which consists of:
 - Batch Code: First 8 characters
 - Data Source Indicator: Next 6 characters
 - Batch Number: Next 10 characters
 - Thread Number: Next 10 characters
 - Line Count (on the DAT file): Next 10 characters
 - Batch Code Description: Next 60 characters

SDBT_BI Triggers

SDBT_BI triggers insert data into the SA_CHANGE_LOG table in preparation for extraction. The triggers use sequence number settings to determine the next batch number for the extraction.

The following triggers are used:

bi_adiu_acct_data	bi_adiu_actg_log
bi_adiu_actperdates	bi_adiu_asset
bi_adiu_assetdown	bi_adiu_auth_stt
bi_adiu_catalog	bi_adiu_dept
bi_adiu_dept_oa	bi_adiu_failure
bi_adiu_op_actg_tr_ty	bi_adiu_ouom
bi_adiu_repair	bi_adiu_rootcause
bi_adiu_rule_key_oex	bi_adiu_rulekey_stt
bi_adiu_storeroom	bi_adiu_strm_setup
bi_adiu_strm_trans	bi_adiu_tracwrkordtcr
bi_adiu_tracwrkordtpl	bi_adiu_wrkord
bi_adiu_wrkordadjust	bi_adiu_wrkordlbr
bi_adiu_wrkordmat	bi_adiu_wrkordrequire
bi_adiu_wrkordservcont	bi_adiu_wrkordtask
bi_adiu_wrkordtfail	bi_adiu_wrkordty

Extracts

The following section maps the extract program to the data that it handles as well as the view, batch procedure and trigger that are used to complete the extraction.

Please refer to the extract mapping document titled, WAM BI Extract Mapping for more information.

To Review the Columns that are Extracted

Access the database and describe the definition of the view. From there you can see the specific columns that comprise the view.

For example, in SQL Plus:

SELECT * FROM SYNERGEN.SV_BI_EXTRACT_EXTDFAIL Vw