

Islamic Accounts User Guide

Oracle FLEXCUBE Universal Banking

Release 12.0.2.4.4

February 2015

Islamic Accounts User Guide
February 2015
Oracle Financial Services Software Limited

Oracle Park

Off Western Express Highway
Goregaon (East)
Mumbai, Maharashtra 400 063
India

Worldwide Inquiries:

Phone: +91 22 6718 3000

Fax: +91 22 6718 3001

www.oracle.com/financialservices/

Copyright © 2007, 2015, Oracle and/or its affiliates. All rights reserved.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate failsafe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

This software or hardware and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

Contents

| | |
|---|------------|
| 1. Preface | 1-1 |
| 1.1 Introduction..... | 1-1 |
| 1.2 Audience..... | 1-1 |
| 1.3 Documentation Accessibility..... | 1-1 |
| 1.4 Organization | 1-1 |
| 1.5 Related Documents..... | 1-1 |
| 1.6 Glossary of Icons..... | 1-2 |
| 2. Creating Islamic Accounts | 2-1 |
| 2.1 Introduction..... | 2-1 |
| 2.2 Maintaining Islamic Account Class..... | 2-1 |
| 2.2.1 <i>Account Details Tab</i> | 2-3 |
| 2.2.2 <i>Statement Parameters Tab</i> | 2-7 |
| 2.2.3 <i>Capturing Additional Details</i> | 2-11 |
| 2.2.4 <i>Specifying Restrictions Details</i> | 2-12 |
| 2.2.5 <i>Maintaining Exclusion Criteria for Profit Sharing</i> | 2-13 |
| 2.2.6 <i>Specifying Branch/Currency Restriction Details</i> | 2-13 |
| 2.2.7 <i>Maintaining Branch Preferences</i> | 2-14 |
| 2.2.8 <i>Maintaining Currency Preferences</i> | 2-14 |
| 2.2.9 <i>Specifying Customers/Categories Details</i> | 2-15 |
| 2.2.10 <i>Specifying MIS Details</i> | 2-16 |
| 2.2.11 <i>Specifying Preferences Details</i> | 2-17 |
| 2.2.12 <i>Specifying REG Details</i> | 2-21 |
| 2.2.13 <i>Specifying Deposit Details</i> | 2-22 |
| 2.2.14 <i>Specifying Auto Deposit Details</i> | 2-23 |
| 2.2.15 <i>Specifying GL Lines Details</i> | 2-24 |
| 2.2.16 <i>Specifying Status Rule Details</i> | 2-26 |
| 2.2.17 <i>Specifying Amount Block Details</i> | 2-28 |
| 2.2.18 <i>Specifying Statement Details</i> | 2-29 |
| 2.2.19 <i>Time Interim Transactions Report</i> | 2-31 |
| 2.2.20 <i>Times – Balance Report</i> | 2-31 |
| 2.2.21 <i>Specifying Notice Details</i> | 2-31 |
| 2.2.22 <i>Specifying Fields Details</i> | 2-33 |
| 2.2.23 <i>Triggering a Batch for Accounts Eligible for Profit Sharing</i> | 2-33 |
| 2.3 Maintaining Islamic Customer Accounts..... | 2-34 |
| 2.3.1 <i>Main Tab</i> | 2-37 |
| 2.3.2 <i>Auxiliary Tab</i> | 2-43 |
| 2.3.3 <i>Nominee Tab</i> | 2-51 |
| 2.3.4 <i>Check List Tab</i> | 2-52 |
| 2.3.5 <i>Capturing Additional Details</i> | 2-54 |
| 2.3.6 <i>Specifying Profit Details</i> | 2-56 |
| 2.3.7 <i>Specifying Charges Details</i> | 2-58 |
| 2.3.8 <i>Specifying Consolidated Charges Details</i> | 2-59 |
| 2.3.9 <i>Specifying BIC Details</i> | 2-60 |
| 2.3.10 <i>Specifying Deposits Details</i> | 2-61 |

| | | |
|-----------|---|------------|
| 2.3.11 | <i>Specifying Instructions Details</i> | 2-62 |
| 2.3.12 | <i>Specifying Standing Instructions Details</i> | 2-63 |
| 2.3.13 | <i>Specifying Linked Entities Details</i> | 2-63 |
| 2.3.14 | <i>Specifying REG Details</i> | 2-64 |
| 2.3.15 | <i>Specifying Account Status Details</i> | 2-66 |
| 2.3.16 | <i>Specifying Restrictions Details</i> | 2-67 |
| 2.3.17 | <i>Specifying Currency Limits Details</i> | 2-70 |
| 2.3.18 | <i>Specifying MIS Details</i> | 2-71 |
| 2.3.19 | <i>Specifying Change Log Details</i> | 2-72 |
| 2.3.20 | <i>Specifying Cheque Book Request Details</i> | 2-74 |
| 2.3.21 | <i>Specifying Card Request Details</i> | 2-75 |
| 2.3.22 | <i>Specifying Linked Deposit Details</i> | 2-76 |
| 2.3.23 | <i>Specifying Statement Details</i> | 2-77 |
| 2.3.24 | <i>Specifying Limits Details</i> | 2-83 |
| 2.3.25 | <i>Specifying Joint Holders Details</i> | 2-86 |
| 2.3.26 | <i>Specifying UDF Details</i> | 2-88 |
| 2.3.27 | <i>Specifying Deposits Instruction Details</i> | 2-88 |
| 2.3.28 | <i>Specifying Billing Parameters Details</i> | 2-90 |
| 2.3.29 | <i>Specifying Account Signatory Details</i> | 2-92 |
| 2.3.30 | <i>Specifying Interim Transactions Report Details</i> | 2-93 |
| 2.3.31 | <i>Specifying Interim Transactions Report</i> | 2-93 |
| 2.3.32 | <i>Specifying Notice Details</i> | 2-95 |
| 2.3.33 | <i>Specifying Cards Details</i> | 2-96 |
| 2.3.34 | <i>Specifying OFAC Check Details</i> | 2-97 |
| 2.3.35 | <i>Specifying Change Log Details</i> | 2-99 |
| 2.3.36 | <i>Maintaining Provisioning Preferences for a Islamic account</i> | 2-100 |
| 2.3.37 | <i>Maintaining Provisioning Percentages Details</i> | 2-100 |
| 2.3.38 | <i>Viewing details of Amounts and Dates</i> | 2-101 |
| 2.3.39 | <i>Viewing Total Available Balance Details</i> | 2-102 |
| 2.3.40 | <i>Viewing Turnover Amounts</i> | 2-102 |
| 2.3.41 | <i>Maintaining Other Details for Islamic Deposit Account</i> | 2-103 |
| 2.3.42 | <i>Closing a Islamic Account</i> | 2-104 |
| 2.3.43 | <i>Executing Automatic Closure Batch</i> | 2-105 |
| 2.3.44 | <i>Sweep In and Sweep Out Batch Processing</i> | 2-107 |
| 2.3.45 | <i>Generating Alert for Secure Overdraft Utilization</i> | 2-107 |
| 2.3.46 | <i>Creating a Message Advice Format</i> | 2-108 |
| 2.4 | <i>Viewing Islamic Customer Accounts Details</i> | 2-109 |
| 2.5 | <i>Viewing Mudarabah Sweep Details</i> | 2-111 |
| 3. | Maintaining Investment Weights | 3-1 |
| 3.1 | <i>Introduction</i> | 3-1 |
| 3.2 | <i>Maintaining Investment Weights</i> | 3-1 |
| 3.3 | <i>Profit Calculation Batch</i> | 3-3 |
| 3.4 | <i>Updating Profit Calculation</i> | 3-5 |
| 3.5 | <i>Profit Distribution Batch</i> | 3-8 |
| 3.5.1 | <i>Period Code</i> | 3-9 |
| 3.5.2 | <i>Total Investment</i> | 3-9 |
| 3.5.3 | <i>Total Profit</i> | 3-10 |
| 3.5.4 | <i>Profit Equalization Amount</i> | 3-11 |
| 3.6 | <i>Profit Calculation Exclusion Batch</i> | 3-12 |
| 3.7 | <i>Zakat Batch Process</i> | 3-13 |

| | | |
|-----------|--|------------|
| 3.7.1 | <i>Status Change Batch Processing (CSDSTBTC)</i> | 3-13 |
| 4. | Creating Islamic Term Deposits | 4-1 |
| 4.1 | Introduction | 4-1 |
| 4.2 | Maintaining Term Deposit Account Class | 4-1 |
| 4.2.1 | <i>Specifying Deposit Preferences</i> | 4-2 |
| 4.2.2 | <i>Specifying the Auto Deposits</i> | 4-4 |
| 4.3 | Setting Up Profit Preferences for TD | 4-6 |
| 4.3.1 | <i>Linking TD Account Class to Profit Product</i> | 4-7 |
| 4.4 | Creating Islamic TD | 4-8 |
| 4.4.1 | <i>Main Tab</i> | 4-9 |
| 4.4.2 | <i>Nominee Tab</i> | 4-12 |
| 4.4.3 | <i>Deposit Tab</i> | 4-13 |
| 4.4.4 | <i>Dual Currency Deposit Tab</i> | 4-18 |
| 4.4.5 | <i>Check List Tab</i> | 4-20 |
| 4.4.6 | <i>Capturing Additional Details</i> | 4-22 |
| 4.4.7 | <i>Specifying IP Special Condition Details</i> | 4-24 |
| 4.4.8 | <i>Specifying TD Payout Details</i> | 4-25 |
| 4.5 | Viewing Islamic TD Account Details | 4-27 |
| 4.6 | Redeeming TD | 4-29 |
| 4.6.1 | <i>Bank - Cheque Tab</i> | 4-32 |
| 4.6.2 | <i>Savings Tab</i> | 4-33 |
| 4.6.3 | <i>General Ledger Tab</i> | 4-34 |
| 4.6.4 | <i>Authorizing Transaction</i> | 4-35 |
| 4.7 | Viewing TD Redemption Details | 4-36 |
| 4.8 | Redeeming TD Partially | 4-37 |
| 5. | Reports | 5-1 |
| 5.1 | Introduction | 5-1 |
| 5.2 | Mudarabah Monthly Average Balance Report on Month End for Savings | 5-1 |
| 5.2.1 | <i>Contents of the Report</i> | 5-1 |
| 5.3 | Mudarabah Monthly Average Balance Report on Profit Distribution Date for Savings | 5-2 |
| 5.3.1 | <i>Contents of the Report</i> | 5-3 |
| 5.4 | Mudarabah Monthly Minimum Balance Report on Month End for Savings | 5-4 |
| 5.4.1 | <i>Contents of the Report</i> | 5-4 |
| 5.5 | Mudarabah Monthly Minimum Balance Report on Profit Distribution Date for Savings | 5-5 |
| 5.5.1 | <i>Contents of the Report</i> | 5-6 |
| 5.6 | Mudarabah Quarterly Average Balance Report for Savings | 5-7 |
| 5.6.1 | <i>Contents of the Report</i> | 5-8 |
| 5.7 | Mudarabah Quarterly Minimum Balance Report for Savings | 5-9 |
| 5.7.1 | <i>Contents of the Report</i> | 5-10 |
| 6. | Annexure A - IP Rule Set-up | 1-1 |
| 6.1 | Introduction | 1-1 |
| 6.2 | IP Rule Maintenance | 1-1 |
| 6.3 | UDE Value Maintenance | 1-3 |
| 6.3.1 | <i>TD with Capitalization</i> | 1-4 |
| 6.3.2 | <i>Normal TD with Simple Profit</i> | 1-4 |
| 6.3.3 | <i>Recurring Deposit Scheme</i> | 1-5 |
| 7. | Function ID Glossary | 2-1 |

1. Preface

1.1 Introduction

This manual is designed to help you quickly acquaint yourself with the Islamic Accounts module of Oracle FLEXCUBE. It provides information on creating Islamic accounts in Oracle FLEXCUBE.

You can obtain information specific to a particular field by placing the cursor on the relevant field and striking <F1> on the keyboard.

1.2 Audience

This manual is intended for the following User/User Roles:

| Role | Function |
|---------------------------------------|--|
| Back office managers/officers | Authorization functions |
| Product Managers | Product definition and authorization |
| End of day operators | Processing during end of day/ beginning of day |
| Financial Controller/Product Managers | Generation of reports |

1.3 Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc>.

1.4 Organization

This manual is organized into the following chapters:

| | |
|------------------|--|
| Chapter 1 | <i>About this Manual</i> gives information on the intended audience. It also lists the various chapters covered in this User Manual. |
| Chapter 2 | <i>Creating Islamic Accounts</i> explains how you can create Islamic Deposit Accounts. |
| Chapter 3 | <i>Maintaining Investment Weights</i> explains to process to capture the risk associated with every investment to compute the profit distribution. |
| Chapter 4 | <i>Creating Islamic Term Deposits</i> describes the process to setup and maintain term deposit account facilitated by Oracle FLEXCUBE. |
| Chapter 5 | <i>Reports</i> provides a list of reports that can be generated in this module and also explains their contents. |
| Chapter 6 | <i>Annexure A - IP Rule Set-up</i> lists the Profit and Charge (IP) rules which are to be maintained for the Islamic TD module of Oracle FLEXCUBE. |
| Chapter 7 | <i>Function ID Glossary</i> has alphabetical listing of Function/Screen ID's used in the module with page references for quick navigation. |

| | |
|--|--|
| | |
|--|--|

1.5 Related Documents

- The Core Entities User Manual
- The Procedures User Manual
- The Settlements User Manual
- The Profit and Charges User Manual

1.6 Glossary of Icons

This User Manual may refer to all or some of the following icons.

| Icons | Function |
|--|-------------|
|  | Exit |
|  | Add row |
|  | Delete row |
|  | Option List |

2. Creating Islamic Accounts

2.1 Introduction

As part of capturing customer related information in Oracle FLEXCUBE you need to maintain Customer Information Files (CIF records) for each entity who is a customer of your bank. Apart from creating CIF records for each entity you need to maintain separate accounts for each customer. The features of these two screens have been discussed in detail in the preceding sections.

While defining Islamic Deposit Accounts, you would have noticed that many of the fields have option lists positioned next to them. While some option lists contain pre-defined values for some option lists to be populated you need to capture data through separate screens. For instance, each Islamic deposit account needs to be associated with an Islamic account class. Therefore, you will need to maintain Islamic account class before you start defining Islamic deposit accounts.

All such screens have been documented in the subsequent sections.

2.2 Maintaining Islamic Account Class

In the 'Islamic Account Class Maintenance' screen, where you open Islamic deposit accounts for the customers of your bank, each customer account is linked to an Islamic deposit account class, and the attributes defined for the account class are by default applicable to the customer account. For instance, if the frequency of account statement generation has been defined as daily for Islamic account class, the system generates statements for all accounts under this class on a daily basis. However, some of the parameters defined for the account class, can be revised at the account level for any of the accounts linked to the class. Account level parameters will supersede those defined for the account class.

While defining the Islamic account classes you should also keep in mind, that the profit rate structure is also specified for an account class (in the Profit and Charges module).

The account class table is maintained at the Bank Level by the Head Office branch.

You can invoke the 'Islamic Account Class Maintenance' screen by typing 'IADACCLS' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Defining Islamic Account Class includes the maintenance of the following parameters:

Account Class and Description

The Account Class code is a unique code, which identifies the class. Along with the class code you need to assign an appropriate description to the account class.

For instance, let us assume you are defining a class for deposit account of individuals. You could associate the code DEP IND with it. Similarly, the description that you associate with it could be something like this – 'Deposit accounts of individuals'.

Account Type

By default the account type is 'Deposit'. You will not be able to modify this option.

Start Date

When you create a Islamic account class, you can specify the life span of the account class by indicating the start date.

The start date for an account class refers to the start date for which, creation of new account under the account class is allowed.

Consequently, the option list for Islamic account class in all further transactions screen in Oracle FLEXCUBE, will display the account class as of the system date.

End Date

When you create a Islamic account class, you can also specify the life span of the account class by indicating the end date.

The end date for an account class refers to the termination date after which, creation of new account under the account class is disallowed.

Consequently, the option list for Islamic account class in all further transactions screen in Oracle FLEXCUBE, will not display the 'expired' account class as of the system date. However, the existing accounts for the account class will be active even after the end date.

Note

If you do not specify an End Date for the account class, the account is taken to be an open-ended account class.

2.2.1 **Account Details Tab**

The 'Account Details' tab is displayed, by default, in the 'Islamic Accounts Class Maintenance' screen. The fields in the Account Details section are as follows:

Account Code

As per your bank's requirement you can choose to classify Islamic account class into different account codes. The bank can decide the manner in which the account classes are to be assigned to different account codes. An account code can consist of a maximum of four characters.

Depending on the customer account mask maintained, the value in the account code field would be used during the generation of customer account numbers through the 'Islamic Customer Accounts Maintenance' screen.

If you have decided to include account code as part of the customer account number (in the account number mask), then at the time of creating a new customer account number, you will need to select the account class for the account number being generated. In the option-list provided, the account class is displayed along with the associated account code. When the account number gets populated, it is the account code that forms a part of the customer account number.

Dormancy Days

You have to indicate the period after which an account in an Islamic account class becomes inactive or dormant if customer transactions are not posted into the account. The system allows only four numeric characters for Dormancy Days.

Note

However, while maintaining transaction codes, if you have checked the Consider for Account Activity field, all transactions posted to any account under this account class linked to the particular transaction code will become active from dormant irrespective of the dormancy period. If a customer-initiated transaction is posted into the account with the dormant status the account status will be updated to Active from Dormant since the Transaction Code associated with the account has the Consider for Account Activity option enabled.

Account Statement Format

Choose 'ACST_DETAILED' for Savings type of account class and Nostro type of account class.

Display IBAN in Advices

For an Islamic account class you can indicate whether the IBAN number of the customers involving the accounts within the class should be printed on advices sent to the customer. If you would like to print the IBAN number of the customers on advices sent to the customers involving the account class, you can enable the 'Display IBAN in Advices' option by checking it.

Your specification will be made applicable to all customers linked to the account class. You will be allowed to change this option for a specific account.

Note

IBAN Account numbers for specific customers can be captured while defining a specific account through the IBAN Sub-screen of the 'Islamic Customer Account Maintenance' screen.

Interpay

Check this box if you wish to interpay.

Natural GL

The reporting of all turnovers of the particular Islamic account class will be directed to the GL that you identify as the natural GL. Based on the characteristic of the account balance, you can specify whether the turnover is to be posted to the Debit GL or to the Credit GL. For instance, if the account class is for overdrafts, the balance is normally a debit whereas current accounts normally do not have a debit balance.

Dormancy Parameters

As stated above, if transaction code associated with the account has the 'Consider for Account Activity' option enabled, the dormant status of the account will be updated to 'Active'. Apart from this, you can specify the parameter that is required for re activating the account. To indicate the re activation parameters for the dormant account choose any from the following options:

- Debit
- Credit
- Any
- Manual

In case of a transaction, the system will check for the parameter you have specified here and accordingly change the status of the account. However, the parameter maintained at the account level will supersede the parameter you have specified here.

Applicable Customer Status

Specify the applicable customer status from the drop-down list. The available options are:

- Major
- Minor
- Both
- Not Applicable

Note

By default 'Not applicable' option would be selected when a new account class is created.

If you select 'Minor' option at the CIF level and 'Applicable customer status' as 'Major' at the account class level then the system displays an error message as, "The A/c class you selected is for major customer."

Similarly if you uncheck 'Minor' option at the CIF level and select 'Applicable customer status' as 'Minor' at the account class level then the system displays an error message as, "The A/c class you selected is for minor customer."

Charges

Specify the following details.

Charge Start Advice

You can use this field to indicate whether a charge start advice is to be sent to the customer, indicating the commencement of charging on accounts under the account class.

Charging on the accounts under the class would commence on the charge start date specified for the account. The charge start advice would be sent, a specified number of days in advance (the Advice Days) of the charge start date.

Advice Days

If you have indicated that a charge start advice is to be sent to the customer, indicating the commencement of charging on accounts under the account class, specify the number of days before the charge start date, the charge start advice is to be sent.

Free Period

Specify the number of days after the account opening date, which constitute the free banking period for accounts under the class. During the free banking period, no charges are applied on the account.

Provisioning Details

When you define an account class, you can specify whether provisioning is applicable for accounts using the class. You can make the following specifications in the Provisioning Details section in the 'Account Classes' screen:

Required

Check this box if provisioning is applicable.

Provisioning Frequency

Select the frequency at which the provisioning would be done either daily or monthly.

Note

The frequency you define here is only applicable if you have indicated individual account-wise status processing for accounts in the Branch Parameters. If you have indicated status processing at Group/CIF level, then the provisioning batch process executes at the frequency maintained in the 'Branch Parameters' screen for your branch, and not at the frequency maintained in the Account Classes screen.

Provision Currency

You can indicate the currency in which the provisioning amount must be calculated – either account currency or local currency. This specification is defaulted from the preferences for the Islamic account class used by the account, and you can alter it if necessary.

Exposure Category

If the logic for deriving the exposure category of the CIF or customer group to which the customer belongs, based on the total exposure, has been maintained in the Exposure Type Category Linkage maintenance, then the exposure category of the account is identified. If no logic has been maintained, you can specify the exposure category in the 'Islamic Account Class Maintenance' screen.

Event Class Code

Specify the event class for which the provisioning accounting entries would be defined.

Liquidation Days

Specifies the number of working days from the actual liquidation date before the profit / charge can be liquidated into the customer account. Working days are calculated on the basis of the Local Holiday Calendar.

Liquidation Mode

Debit profit or charges can be liquidated either Manually or Automatically. If you choose the automatic mode of liquidation, debit profit or charges are liquidated automatically as part of the BOD process on the liquidation date. However, after having specified Auto as the mode of liquidation, if you wish to liquidate them manually for a specific account, the System intimates you with an override message. Manual profit liquidation can be triggered through the 'Debit Profit Liquidation' screen. Manual liquidation is recommended during Account Closure.

Note

- You will not be allowed to change these preferences at the account level. However in the Amounts and Dates section of the 'Islamic Customer Accounts Maintenance' screen, both the total debit profit due as well as the charges due, are displayed.
 - If there is any outstanding profit or charges on the account, the outstanding amount is displayed as an override while saving the transaction involving the account.
 - While closing an account closure, the system verifies whether there is any outstanding debit profit or charges on the account. You will need to liquidate these before account closure.
 - An error log is created to store the error details of accounts for which liquidation could not be performed due to the following reasons:
 - The Verify Funds option is enabled and partial liquidation is performed.
 - The Verify Funds option is enabled and the account has insufficient funds.
 - Accounting entries do not get passed successfully irrespective of whether the Verify Funds option is set or not.
-

Refer the End of Day processing for Debiting Receivable GLs section in the Daily Processing of IP chapter of the IP User Manual for details on end of day processes on Auto and Manual liquidation.

Escrow Details

The following Escrow details can be maintained for the account class:

Escrow Transfer Applicable

This box is checked by default, when an account is created. Uncheck this box if Escrow transfer is not applicable.

Transaction Code

Select the Transaction Code to be used for Escrow transfer from the adjoining option list. The option list displays only those transaction codes which are enabled for Escrow processing at the 'Transaction Code Maintenance' screen.

Note

This is a mandatory input if Escrow transfer is enabled for the account class.

Transaction Code for Reversal

Select the transaction code to be used for Escrow Reversal transactions from the adjoining option-list. The option list displays only those transaction codes which are enabled for Escrow processing at the 'Transaction Code Maintenance' screen.

Note

During account class amendment system does not allow you to disable Escrow process for an account class if a Project account has been created using that account class.

Cash Deposit Limit on Trust Account

If you have checked the box 'Escrow Transfer Applicable', you will have to specify the maximum cash that can be deposited in the Trust accounts under this account class.

2.2.2 Statement Parameters Tab

For each Islamic account class that you maintain you have the option of generating account statement details, periodically, for all customer accounts associated with the account class.

If you need to generate account statements that would need to be sent across multiple media, generated at different frequencies, you can define up to three different frequencies at which the statements could be generated, with a primary, secondary and tertiary frequency.

Note

If you are defining primary, secondary and tertiary statements, the frequency for each must be different and unique; for instance, if you define a monthly primary statement, you cannot define a secondary or tertiary statement with a monthly frequency.

As part of specifying the account statement preferences you can indicate the following for each of the statements, whether primary, secondary or tertiary.

Click 'Statement Parameters' tab in the 'Islamic Accounts Class Maintenance' screen. The fields in the Statement Parameters section are as follows:

The screenshot shows the 'Account Class Maintenance' application window. The 'Statement Parameters' tab is active. The window contains the following sections:

- Account Details:** Account Class, Description, Account Type (Current), Start Date, End Date.
- Primary Account Statement Parameters:** Type (None, Summary, Detailed), Cycle, On, Offline Limit.
- Secondary Account Statement Parameters:** Type (None, Summary, Detailed), Cycle, On.
- Tertiary Account Statement Parameters:** Type (None, Summary, Detailed), Cycle, On.
- Document List:** A table with columns Document Type, Customer Type, and Mandat. The table shows one row with 'Individual' as the Customer Type and 'Yes' as the Mandat.
- Document Notification Details:** Send Notification checkbox, Frequency (Select), Days (Reminder).

The bottom of the window has a status bar with fields for Maker, Checker, Date Time, Mod No, Record Status, and Authorization Status, along with an 'Exit' button.

Specify the following details:

Primary Account Statement Parameters

Indicate the following details.

Type

The first preference that you specify for Islamic account class is to indicate whether the periodic generation an account statement is required. If the generation of an account statement is necessary, you have to specify the format in which it is to be generated. The options available are:

- None
- Detailed – indicating that the statement should be a detailed account of all the customer transactions within the account class.
- Summary – indicating that only a summary of the transaction details is enough.

Cycle

The system generates the account statement details at a frequency that you specify. The frequency can be:

- Annual
- Semi-annual
- Quarterly
- Monthly
- Fortnightly
- Weekly
- Daily

If you indicate that the statement generation frequency is weekly, you should also indicate the day of the week on which the account statement is due. Similarly, for a monthly statement you should indicate the day of the month.

On

To specify the frequency for a monthly statement you can specify a number between 1 and 31 (corresponding to the system date). If you set the statement date to 30, then account statements will be generated on:

- The last working day for months with < 30 days
- For months with 30 days on the 30th; if 30th is a holiday on the next working day

If you set the statement date to 31, then account statements will be generated on:

- The 31st, for month with 31 days; if 31st is a holiday on the next working day
- The last working day for months < 31 days

For all other cycles, account statement would be generated on the last day of that cycle.

Offline Limit

This is the limiting amount till which transactions will be carried out between account(s) for the account class you are defining here, between branches when the database connectivity is not functional.

Enter the off-line limit here.

Note

- If you are defining primary, secondary and tertiary statements, the frequency for each must be different and unique; for instance, if you define a monthly primary statement, you cannot define a secondary or tertiary statement with a monthly frequency.
 - Offline limit is maintained only for primary level
-

Tertiary Account Statement Parameters

Indicate the following details.

Type

The first preference that you specify for Islamic account class is to indicate whether the periodic generation an account statement is required. If the generation of an account statement is necessary, you have to specify the format in which it is to be generated. The options available are:

- None
- Detailed – indicating that the statement should be a detailed account of all the customer transactions within the account class
- Summary – indicating that only a summary of the transaction details is enough

Cycle

The system generates the account statement details at a frequency that you specify. The frequency can be:

- Annual
- Semi-annual
- Quarterly
- Monthly
- Fortnightly
- Weekly
- Daily

If you indicate that the statement generation frequency is weekly, you should also indicate the day of the week on which the account statement is due. Similarly, for a monthly statement you should indicate the day of the month.

On

To specify the frequency for a monthly statement you can specify a number between 1 and 31 (corresponding to the system date). If you set the statement date to 30, then account statements will be generated on:

- The last working day for months with < 30 days
- For months with 30 days on the 30th; if 30th is a holiday on the next working day
- If you set the statement date to 31, then account statements will be generated on:
 - The 31st, for month with 31 days; if 31st is a holiday on the next working day
 - The last working day for months < 31 days

For all other cycles, account statement would be generated on the last day of that cycle.

Secondary Account Statement Parameters

Indicate the following details.

Type

The first preference that you specify for Islamic account class is to indicate whether the periodic generation an account statement is required. If the generation of an account statement is necessary, you have to specify the format in which it is to be generated. The options available are:

- None
- Detailed – indicating that the statement should be a detailed account of all the customer transactions within the account class
- Summary – indicating that only a summary of the transaction details is enough

Cycle

The system generates the account statement details at a frequency that you specify. The frequency can be:

- Annual
- Semi-annual
- Quarterly
- Monthly
- Fortnightly
- Weekly
- Daily

If you indicate that the statement generation frequency is weekly, you should also indicate the day of the week on which the account statement is due. Similarly, for a monthly statement you should indicate the day of the month.

On

To specify the frequency for a monthly statement you can specify a number between 1 and 31 (corresponding to the system date). If you set the statement date to 30, then account statements will be generated on:

- The last working day for months with < 30 days
- For months with 30 days on the 30th; if 30th is a holiday on the next working day
- If you set the statement date to 31, then account statements will be generated on:
 - The 31st, for month with 31 days; if 31st is a holiday on the next working day
 - The last working day for months < 31 days

For all other cycles, account statement would be generated on the last day of that cycle.

Document Check List

Specify the following details:

Document Type

Specify the document type. The adjoining option list displays all the document types that are maintained in the system. You can select the appropriate one.

Customer Type

Specify the customer type. The adjoining option list displays all the customer types that are maintained in the system. You can select the appropriate one.

Mandatory

Check this box to indicate that the document specified here is mandatory.

Document Notification Details**Send Notification**

This check box indicates whether to send notifications or reminders for not submitting the mandatory documents.

Frequency (Notification)

System defaults the frequency of notification to be sent. The frequency can be one of the following:

- Daily
- Weekly
- Monthly
- Quarterly
- Half yearly
- Yearly

Days (Reminder)

System defaults the number of days left for the expiry or submission due date of the documents for sending the reminder.

2.2.3 Capturing Additional Details

You can capture additional details for the Islamic Account Class by clicking the following buttons in the 'Islamic Account Class Maintenance' screen:

| Button | Function |
|-----------------------------|--|
| Restrictions | This invokes the 'Account Class - Product and Transaction Codes Maintenance' screen. |
| Branch/Currency Restriction | This invokes the 'Branch Currency' screen. |
| Customer Categories | This invokes the 'Account Class - Customer List' screen. |
| MIS | This invokes the 'Management Information System' screen. |
| Preferences | This invokes the 'Preferences' screen. |
| REG | This invokes the 'REG Details' screen. |
| Deposit | This invokes the 'Deposit Account Details' screen. |
| Auto Deposit | This invokes the 'Auto Deposits' screen. |

| | |
|-------------|--|
| GL Lines | This invokes the 'GL Lines' screen. |
| Status Rule | This invokes the 'Status Rule Definition' screen. |
| Amt Block | This invokes the 'Amount Block Details' screen. |
| Statement | This invokes the 'Interim Transactions and Balance Report' screen. |
| Notice | This invokes the 'Notice Details' screen. |
| Fields | This invokes the 'User Defined Fields' screen. |

2.2.4 Specifying Restrictions Details

You can place restrictions on transactions involving Islamic accounts, at the account class level. As discussed earlier (for customer account), these restrictions get defaulted to all accounts that are linked to the Islamic account class. But you are allowed to change these restrictions for individual accounts as well.

To maintain the restrictions, click the 'Restriction' button in the 'Islamic Account Class Maintenance' screen. The 'Account Class - Product and Transaction Codes Maintenance' screen is displayed.

The restrictions can be based on:

- Products
- Transaction Codes

Validation of restrictions

During maintenance or online operations, in the respective contract screens for the restricted transactions, when you specify the customer account, the system checks whether the account

class used by the specified account is restricted for the product that has been selected, or the debit / credit transaction type. If so, an override is sought when such contracts are saved.

2.2.5 **Maintaining Exclusion Criteria for Profit Sharing**

You can specify the allowed transaction count for accounts in the account class to be considered for the profit sharing process and also you need to specify the threshold count for every allowed transaction code maintained for the Account Class. In case the transaction count for certain accounts exceeds the stipulated count, then such accounts will not be considered for the purpose of profit contribution and sharing.

Click on 'Exclusion Criteria for Profit Sharing' button in the 'Account Class - Product and Transaction Codes Maintenance' screen to invoke 'Exclusion Criteria For Profit Sharing' screen.

| Transaction Code | Transaction Count |
|------------------|-------------------|
| | |

Here you specify the count threshold for every transaction code maintained in the system

2.2.6 **Specifying Branch/Currency Restriction Details**

In addition to what you have specified in the 'Islamic Account Class Maintenance' screen you have the option of specifying the following for the accounts class:

- List of allowed or disallowed branches and allowed or disallowed currencies
- List of allowed and disallowed customer categories and allowed and disallowed customers

2.2.7 Maintaining Branch Preferences

You can specify the branch and currency preferences through the 'Branch Currency' screen. Click the 'Branch/ Currency Restriction' button in the 'Islamic Account Class Maintenance' screen. The screen will be displayed.

The screenshot shows the 'Branch Currency' window. At the top, there is a text field for 'Account Class'. Below it are two tabs: 'Branch Details' (selected) and 'Currency Details'. Under 'Branch Details', there are radio buttons for 'Branch Restrictions': 'Allowed' and 'Disallowed', with 'Disallowed' selected. Below this is a section titled 'Available Branches' with a search bar and a list of branches. The list has a header 'Branch Code *' and one entry with a checkbox. At the bottom, there is a 'Currency Preferences' section and 'Ok' and 'Exit' buttons.

All the allowed currencies you have defined for this account class will be displayed in the Allowed column. You can enter the minimum balance that should be maintained against each currency. Additionally, you can also enter the currency-wise minimum balance for the profit sharing that should be maintained in the accounts (under the account class) to be eligible for profit sharing.

Customer accounts maintained in any branch can be linked to any account class. However, you have the option of restricting the linkage of customer accounts in a particular branch or branches to an account class.

To specify this, click on disallowed since the disallowed branch list is smaller than the allowed branch list. From the list of Available Branches select 001 and click the adjoining arrow. Repeat the procedure for 004. 001 and 004 will be listed under disallowed branches.

Note

For specifying the allowed list of branches, first click on allowed. You will notice that the list title changes accordingly to allowed and vice versa. You should select allowed or disallowed depending upon the length of the list.

2.2.8 Maintaining Currency Preferences


In this screen you can specify the following for an account class:

- Those branches to which all parameters defined for this account class should be available
- Those currencies in which all customer accounts linked to this account class can operate

For all accounts under this account class you have the option of specifying currencies in which transactions are allowed/disallowed.

For example, you want to restrict all account level transactions under the account class Corporations for corporate type accounts to four important currencies only, say - USD, GBP, JPY, and DEM. You can specify the same. But currency preference needs to be accompanied by specifications regarding the minimum balance limit in each currency.

To do this, click the 'Currency Preferences' button in the 'Branch Currency' screen to invoke 'Currency Preferences' screen.



| Currency Code * | Minimum Balance | ATM Cash Limit | ATM Transaction Limit | Minimum Balance Profit Sh: |
|-----------------|-----------------|----------------|-----------------------|----------------------------|
|-----------------|-----------------|----------------|-----------------------|----------------------------|

For every allowed currency, you can enter the minimum balance that should be maintained against each currency. Additionally, you can specify the limit for performing cash transactions in an ATM. You can also enter the currency-wise minimum balance for the profit sharing that should be maintained in the accounts (under the account class) to be eligible for profit sharing. You can also specify the cash reserve ratio (CRR percentage) for different currencies. Amount as per this ratio will be deducted from the account balance before applying weights. If the box 'Escrow Transfer Applicable' is checked for the account class, you can capture currency-wise cash deposit limit for the Trust accounts linked to the account class.

2.2.9 Specifying Customers/Categories Details

Instead of linking each customer account to the account class, a customer category is linked to the class.

For an account class you should specify the category that should be linked to it and also specify if all customers under each of the categories are to be linked to the account class. In the 'Account Class - Customer List' screen you have the option of specifying the categories that should be linked to this account class and within a category you can also restrict individual customers to be linked to the class.

To indicate allowed customer categories click the 'Customers/ Categories' button. The 'Account Class - Customer List' screen will be invoked.

In this screen you define the following:

- A list of allowed or disallowed customer categories
- A list of disallowed customers (if any) under the allowed category

For an account class you need to specify the customer categories that should be linked to it and also customers within a category who should not be allowed to be linked to this account class.

Note

Check the square box to allow a customer the parameters assigned to this account class. Leave the box unchecked to disallow a customer from being assigned to this account class.

2.2.10 Specifying MIS Details

To invoke the MIS details screen for an account, click the 'MIS' button while opening/modifying the account. The entities defined for the customer will be picked up by default and these entities can be changed.

For an account, the transaction type of MIS class will be picked up from the account class, along with the cost codes and pool codes. The composite type of MIS class will be defaulted from those defined for the customer. These too can be changed.

2.2.11 Specifying Preferences Details

To set preferences, click the 'Preferences' button in the 'Islamic Account Class Maintenance' screen. The 'Preferences' screen is displayed.

Preferences are the options or attributes that uniquely distinguish an account class. The following are the preferences that you can specify for Islamic account class:

- Limit Check – You can check this box to indicate that a limit check for sufficient availability of funds in the account will be made for all accounts belonging to the account class.
- Overdraft Facility – If checked, it indicates that all accounts belonging to this class would be allowed an overdraft facility (facility to draw a specified amount over and above the balance in the account).
- Passbook Facility – If checked, it indicates that accounts linked to the account class are issued passbooks.
- Track Receivable – If checked, you can choose to block the subsequent credit that happens to the settlement account (linked to this account class) of a finance contract or retail teller contract, if the system detects insufficient funds in the account, during liquidation. In other words, the system will track the account for receivables (credits). As and when a credit happens, the funds will be allocated to the finance or the retail teller contract for liquidation.
- Account Statistics - You can enable printing statistics in respect of accounts using an account class, either period code-wise or financial year-wise, for the following customer information:

- Low and High Balance for a period - The lowest and highest current balances for the period.
- Average credit and debit balance for a period - This is computed as the sum of credit / (debit) current balances in a period, divided by the number of days of credit/(debit) balance during the period.
- Credit and debit days - The number of days the account was in credit/ (debit) balance in the period.
- Credit and Debit Turnover - The credit/(debit) turnover for the period.
- Excess days in debit balance - The number of days in a month when the account exceeded the overdraft limits
- Overdraft Limit - This is computed by summing the temporary overdraft limit and the sub-limit of the account. For each month, this would represent the limit on the last date of the month.
- Credit grade of the Customer - This would be the prevalent rating on the last day of the period. For the current period, this information is provided up to the previous working day.

To enable printing of this information for all accounts using the account class, you must enable the Account Statistics option in the 'Islamic Account Class Maintenance' screen.

For each account class for which account statistics has been enabled, an accounting End of Day (EOD) process updates the statistics table both period-wise and according to financial years. The book-dated balances are used for computation of statistics, and the balances are maintained according to accounting periods.

For information about viewing the period-wise account statistics, refer the section Querying on Account Statistics, found earlier in this chapter.

- Exclude Same Day Reversal transaction from Statement - If you do not wish transactions booked and reversed on the same day to be reflected in the account statement, you can specify the preference here. This feature is applicable only for the customer account legs and not for the related GL legs. Also, reversals made through the DE module will not be considered for exclusion. Your specification for this at the account class level defaults to all accounts involving the class. You can change it for a specific account. For comparing transactions the system will look for similarity of reference number and date.
- Back Period Entry Allowed –If checked, indicates that back-valued entries can be posted to account belonging to the class as long as the account is open. You will be allowed to change this specification for a specific account. While posting back-valued transactions, the system verifies whether the 'Back Period Entry Allowed' option has been enabled for the account class. If the option has not been enabled an error message is displayed. This check is also performed while uploading journal entry transactions.
- Profit Statement - Check this box to generate the profit statement.
- Available Balance Check Required – Check this box to indicate available balance is required or not
- Referral Required - Enabling this option indicates whether a referral check should be performed on accounts belonging to the account class. Consequently, the system checks the available balance (not the current balance) while performing the referral checks for all transactions involving the account. If a transaction involving the account results in the account moving to overdraft, the account and transaction details will be sent to the Referral Queue.
- Status Change Automatic - If you check this option, the status of the account will be changed automatically by the system as per the conditions maintained in the 'Status Rule Definition' screen. If you do not select this option, you have to change the status

manually through the 'Manual Status Change' screen. These screens are discussed in detail in the subsequent sections of this document. This specification will be defaulted to all the accounts reporting to this account class.

- Integrated Liquidity Management – Check this box to generate integrated liquidity management
- ATM – If checked, it indicates that accounts linked to the class will avail the ATM facility
- Consolidation for Inward Clearing - You need to indicate whether or not consolidation is required for inward clearing transactions in a batch at the Account Class level. The indication for this option is carried forward to the 'Islamic Customer Account Maintenance' screen. If this option is unchecked here, it cannot be checked in the 'Islamic Customer Account Maintenance screen'.
- Profit Charges – If checked, it indicates that for profit and charges computation the Profit and Charges module will process accounts linked to this class.
- Track Accrued Profit – If checked, it indicates whether accrued profit in the Profit and Charges module on an account linked to this class, would be considered while computing credit utilization for the account.
- Credit Advices– If checked, indicates that for all accounts belonging to this class, the system will generate a credit advices on profit liquidation. The advices are generated during end of day processing in SWIFT or/and MAIL format. You can also specify this preference through the 'Special Conditions' screen.
- Posting Allowed – If checked, indicates that the account class being created is to be used while creating IRA monetary accounts. Monetary accounts used for IRA need to be distinguished from the other accounts in Oracle FLEXCUBE, so that these accounts do not come up for posting in the other Oracle FLEXCUBE screens.
- Lodgment Book - If you wish to allow orders of lodgment books for all accounts that use this account class, you can indicate so, in the 'Islamic Account Class Maintenance' screen, by selecting the Lodgment Book option.
- Replicate Customer Signature - Check this box to indicate that customer signature should be replicated. On checking this option, the signature of the customer gets defaulted to account level.
- Profit Calculation Balance Basis - You can specify the balance basis on which all accounts under this account class should be considered for Mudarabah profit sharing. You can choose the appropriate option from the following values available in the drop-down list adjoining the field 'Profit Contribution Balance Basis':
 - Monthly Average Balance - This option indicates that the system will check whether or not the average balance in every account (under this account class) is equal to or greater than the minimum balance for profit sharing.
 - Month End Balance - This option indicates that the system will check whether or not the balance on the last day of the month in every account (under this account class) is equal to or greater than the minimum balance for profit sharing.
 - Dly Net Balance & Avg Balance - This method of calculation is similar to the average balance calculation (as explained above) with the only difference that, whenever the day end balance of an account falls below the minimum balance (Not the Minimum balance maintained for profit Sharing) stipulated for the account, the contribution of that days balance will be taken as 'zero' while doing summation for the month. System will not check the Balance arrived from the above method with the Minimum balance maintained for Profit Sharing.
 - Min. Balance - This option indicates that the system will check whether or not the lowest ever balance in every account (under this account class) is equal to or greater than the minimum balance for Profit Sharing.

Based on the balance basis chosen, if the system finds the account balance greater than or equal to the minimum balance for profit sharing (Except for Dly Net Balance & Avg Balance), the system will consider that account for profit sharing.

- Mudarabah Fund ID - You can indicate as to which fund the aggregate account balance of all the customers under this account class will report for the depositor contribution from the option list.
- Processing for consolidation of inward Clearing - During the Inward Clearing process, the consolidated entry for clearing will be passed according to the following grouping:
 - Remitter's Account
 - Clearing Product
 - Instrument Currency
 - Remitter's branch
 - End point

A consolidated clearing entry will be passed using a separate Transaction Code maintained in the 'Clearing Product Preferences' screen. This Transaction Code should be set with Cheque Mandatory option as No in the 'Transaction Code Maintenance' screen.

One consolidated clearing entry will be passed for each of the above groups. Entries will be passed against a common reference no. generated for each of the groups. After the consolidated entry has been passed, each individual instrument will be processed separately to pass charge entries (if applicable) at the transaction level.

Cash Reserve Ratio

Specify the cash reserve ratio that should be maintained for all accounts under this account class. This ratio will be applied on the account balances before applying weights during profit distribution.

Exclude from Distribution

Check this box to indicate that accounts under this account class should be excluded from profit distribution.

No. of Days For Salary Block

Specify the number of days for salary block. At the time of salary credit in to a customer account, the system will place an amount block for the number of days specified here from the date of salary credit. The amount blocked will be equal to the finance installments due during this period.

No of days for Closing Unauthorized Accounts with No Activity

Specify the number of days (inactive days) allowed for closing unauthorized accounts with no activity.

No of days for Closing Authorized Accounts with No Activity

Specify the number of days (inactive days) allowed for closing authorized accounts with no activity.

Cheque Book Preferences

Oracle FLEXCUBE provides you with the facility to automatically trigger the reorder of Cheque Books for all accounts reporting to a specific account class. However, you have the option of changing your preferences at the account level also.

To facilitate automatic reordering of Cheque Books, you have to maintain the following details:

Cheque Book

To indicate that automatic reordering of cheque books should be allowed and for specifying the details for the same, you have to check this option. If not selected, you will not be able to maintain the automatic reordering preferences for the account class.

Auto Reorder of Cheque Book

You have to select this option to specify that automatic reordering of Cheque Books is required for all accounts reporting to this account class. This field will be enabled only if you have checked the 'Cheque Book' option explained above.

Reorder Level

Here, you have to indicate the level at which the reordering of Cheque Book should happen. Automatic reordering will be set off by the system when the unused number of cheque leaves becomes equal to or less than the re-order level that you maintain here. This field will be enabled only if you have indicated that automatic reordering of Cheque Books is required i.e. the 'Auto Reorder of Cheque Book' option is checked.

Reorder Number of Leaves


In this field you have to specify the number of leaves that should be ordered for the new Cheque Book. This field will be enabled only if you have checked the 'Auto Reorder of Cheque Book' option.

Max No. of Cheque Rejections

Specify the maximum number of cheque rejections that can be allowed for an account.

2.2.12 Specifying REG Details

For Islamic account class, you can define whether the Regulation D limits are applicable, and the period over which the limits would be applicable. To invoke 'REG Details' screen, click the 'REG' button in the 'Islamic Account Class Maintenance' screen. You can specify the Regulation D applicability details in this screen.



If you indicate the periodicity of Regulation D applicability as 'Statement Cycle', the restricted transactions would be counted over the primary statement cycle defined for the account class.

The Regulation D applicability details specified for the account class would default to all accounts using the class. However, you can make changes to these details when you set up a customer account that uses the account class.

2.2.13 Specifying Deposit Details

To handle term deposits in Oracle FLEXCUBE, you have to set up an account class of type 'Deposit', in the 'Account Class Maintenance' screen.

Identify the account class you are setting up with a unique code and a brief description. To handle term deposits, choose the Deposit option under Account Type.

Note

Typically, for every deposit scheme you offer at your bank, you would set up a Deposit Type Account Class.

Click the 'Deposit' button to define the parameters for a deposit type account class. The 'Deposit Account Details' screen is displayed.

If you want to allow partial redemption of TDs linked to this account class, you will have to check the box 'Allow Partial Redemption'.

Refer the chapter 'Term Deposit Maintenance' in the 'Term Deposits' User Manual for more details about this screen.

2.2.14 Specifying Auto Deposit Details

You can create an auto deposit in case the balance in the source account is overdrawn. The auto creation of deposits is carried out as an end of day process. For creating an auto deposit, you have to maintain the following parameters:



Account Class

For creating an auto deposit, you have to specify an account class of the deposit. The tenor and profit conditions maintained for the selected account class will be defaulted.

Note

You cannot create an auto deposit if the Account class you have chosen has expired, that is, surpassed the end date maintained for the account class. The system will log an exception in such a case.

Transaction Code

You have to specify the transaction code for the auto creation of the deposit.

Currency

Mention the currency in which the deposit is created.

Minimum Required Balance

The minimum balance indicates that only the amounts above this limit will be used for auto creating deposits. You have to specify the minimum amount that the customer can retain in the account.

Cluster ID

The system displays the cluster id linked with the deposit account class linked to the savings account class.

Break Deposits First

Check the box to indicate whether you want the funds to be moved by breaking deposits before breaking the deposit accounts. If you leave the box unchecked, the funds will be moved first from the linked CASA accounts.

Def Rate Code

Select the code of the differential rate from the adjoining option list.

Def Rate Type

Select the type of differential rate code; whether 'Mid' or 'Buy' or 'Sell'.

Sweep Mode

You can indicate the pattern in which sweep outs are created by selecting any one of the two options:

- Auto – Here the amounts are automatically swept out at the end of day when minimum balance exceeds.
- Manual – You have to manually initiate the sweep. The sweep will execute only those instructions that are specified while account opening/ad hoc.

Break Method

You can choose to maintain any one of the following order of breaking deposits:

- LIFO (Last In First Out)– Indicates that the last created deposit will be broken first
- FIFO (First In First Out) – Indicates that the Earliest Deposit will be broken first
- MAXB (Maximum Balance) – Indicates that the Deposits are broken in descending order of available balance
- MINB (Minimum balance) – indicates that the order of breaking of Sweep / Auto deposit will be done for the Account / Deposit with the Minimum Balance

Provide Profit on Broken Deposits

You have to specify whether you want to provide profit on deposits that were broken prematurely. Check the box to indicate that you want to give the profit for the deposits. Leave it unchecked to indicate otherwise.

2.2.15 Specifying GL Lines Details

In Oracle FLEXCUBE, you can assign different status codes to the account class, which will be applicable to all the accounts under it. The accounts will move from one status to the other based on the number of days they have remained inactive in the system. The status of an account will determine whether the account should be marked as an NPA (Non-Performing Asset) or not.

Further, you can also specify the reporting lines (for GL, Central Bank, and Head Office) to which accounting entries should be passed when an account moves from one status to the other. You can post all debit and credit balances of one account class to a single General Ledger account. Conversely, you also have the option of posting debits and credits to separate GLs.

The status codes and the reporting lines for each status may be defined in the 'Status Details' screen. Click the 'GL Lines' button in the 'Islamic Account Class Maintenance' screen to invoke it.

You can specify the following details in this screen:

Status

You can select the different status codes applicable to the account class, in this field. Use the Add icon to define each status and the attributes for the same. You can use the navigation icons to move from one status to the other.

Only status codes with status type 'Account' will be available in the option-list if the Status Processing Basis is defined as 'Contract/Account' for all branches, in the Branch Parameters. If the Status Processing Basis is defined as 'Group/CIF' level for any branch, then the statuses of type 'Both' are available. In this case, it is mandatory to link all the statuses defined.

On selection of the status, the associated description will be displayed alongside.

Specifying Reporting line Details

You can enter the following details:

Dr and Cr GL Lines

Select the debit GL account, to which all debit balances within a specific account class will report to, when it moves to the status being defined. You can identify the debit GL from the list of existing GLs. Likewise, all credits within a particular account class will report to the GL account that you have identified to track credits.

Dr and Cr Central Bank Lines

Select the Central Bank Debit line to which all debit accounts belonging to an account class should report to when it moves to the selected status. You have maintained Central Bank Debit lines in the 'Reporting Lines Maintenance' screen. You can select the appropriate CB Debit Line from the available option-list.

Similarly, all accounts belonging to an account class, if in credit should report to a Central Bank Credit Line for the selected status. You can identify the CB Credit Line that should be associated with the status from the option-list available.

Dr and Cr Head Office Lines

This is the Debit Head Office GL maintained in the 'Reporting Lines Maintenance' screen to which all accounts belonging to this class will report, if they move to the status being defined.

Similarly, select the Credit Head Office GL maintained in the 'Reporting Lines Maintenance' screen to which all accounts belonging to this class will report to, when they move to the status being defined.

Note

As a mandatory requirement, you have to associate the status 'NORM' (Normal) when maintaining status codes for an account class.

Accounting Roles and Heads for Provisioning

In addition to the provisioning preferences that you specify for an account class, you must also maintain the accounting roles and heads representing the GLs to which the accounting entries for provisioning must be passed, for each account status. You can maintain this information in the 'Status Details' screen, when you define each of the status codes.

Rebook Provisioning on Status Change

In the 'Status Details' screen, you can indicate whether provisioning entries for an account must be rebooked when provisioning is done after an automatic status change for the account. Rebooking essentially means that fresh provisioning is done, after writing back the previous provisioning amount.

The provisioning batch process, when executed, not only computes the provisioning amount; it also records the current status of the account and checks whether the current status is different from the status that was prevalent when the process was previously executed. If so, the old provisioning amount is reversed (*if* the Rebook Provision option has been set in the Status Details), and the entries for the new provisioning amount are booked into the provisioning and write back GLs maintained for the current status in the Status Details.

If the Rebook Provision has not been set, there is no reversal of the old provisioning amount, and the differential provisioning entries are passed, as usual, into the GLs maintained for the new status.

2.2.16 Specifying Status Rule Details

If you have opted for automatic status change for all accounts belonging to an account class, you have to maintain the criteria based on which the system will bring about the status change automatically.

You can define the different criteria in the 'Status Rule Definition' screen. Click the 'Status Rule' button in the 'Islamic Account Class Maintenance' screen to invoke it.

In this screen, you can define five conditions for each status applicable to an account class. An account will be said to be in a specific status if any one of the five conditions associated with the status holds true for an account. Conversely, if all the conditions are false, the account will automatically move to the next available status for which the condition is true.

Elements

The following elements are available based on which you can build a condition for automatic status change. You can associate each of these elements with an account, in the 'Customer Accounts Maintenance' screen.

The set of elements are as follows:

- Frozen
- Dormant
- Nodebits
- Nocredits
- Stoppayment
- Current Status

In addition, the following elements will also be available for processing:

- OD (overdraft) Days
- Inactive Days
- Overline Days
- TOD (Temporary Overdraft) Days
- Customer Classification

Logical Operators


Logical Operators are indicators of certain conditions that you specify while building a rule. These operators are used in combination with the elements discussed earlier. The following is a list of logical operators that you would require to build a status rule:

| | |
|------------|-----------------------|
| AND | The conjunction 'and' |
|------------|-----------------------|

| | |
|------------------|---|
| OR | The conjunction 'or' |
| > | Greater than |
| >= | Greater than or equal to (please note that there is no space between the two symbols) |
| < | Less than |
| <= | Less than or equal to (please note that there is no space between the two symbols) |
| < > | Not equal to (please note that there is no space between the two symbols) |
| = | Equal to |

2.2.17 Specifying Amount Block Details

The allocation of funds will occur as per the product sequence you maintain in the 'Amount Block Details' screen invoked from the 'Islamic Account Class Maintenance' screen. Click the 'Amt Block' button to access this screen.



In this screen, you will specify the sequence of products based on which funds will be made available when a credit is posted to an account with a track receivable option. The sequence number is automatically generated by the system. All authorized products of your bank will be available in the option-list. On selection of the product, the product description will appear alongside.

Whenever a credit happens to an account with a track receivable option, the system will check if the account has any receivable being tracked against it. If yes, the amount is blocked as a receivable and this process continues until the amount needed for liquidation becomes fully available.

The batch process run as part of EOD/BOD will liquidate the loan contract or retail teller contracts.

If the amount received is not sufficient for full liquidation, then depending on the minimum amount required for liquidation, the system would initiate a partial liquidation for loans but for retail teller contracts liquidation will be initiated only when full amount is available.

Note

If insufficient funds are detected in an account with a receivable tracking, the system will trigger the event 'LBLK' indicating that enough funds are not available and that subsequent credits made to the account will be blocked as a receivable.

2.2.18 Specifying Statement Details

Interim Transaction reports are maintained through the 'Interim Transactions and Balance Report' screen. Click the 'Statement' button in the 'Islamic Account Class Maintenance' screen to invoke this screen.

The screenshot shows the 'Interim Transactions and Balance Report' window. It features two main sections: 'Interim Transactions Report' and 'Balance Report'. The 'Interim Transactions Report' section includes checkboxes for 'Generate Message' and 'Generate Message only on Movement', a 'Report Transactions Since' dropdown, and an 'Interim Report Type' dropdown. Below these are two data grids: 'Minimum Debit Amount' and 'Minimum Credit Amount'. Each grid has a 'Currency *' column and an 'Amount' column, with a 'Go' button and navigation arrows above them. The 'Balance Report' section includes a 'Generate Balance Report' checkbox and a 'Report Transactions Since' dropdown followed by an 'Of' dropdown. At the bottom, there are tabs for 'Times - Interim Transactions Report' and 'Times - Balance Report', and 'Ok' and 'Exit' buttons.

Specifying Interim Transactions Report

Generate Message

Check this box to indicate that the periodic interim statement (MT942) generation is required for the account. The 'Consolidated Statement' and 'Generate Message' are mutually restricted.

Generate Message Only on Movement

Check this box to indicate that the interim statement generation is required, only if additional entries have been posted subsequent to the previous interim statement generation.

Report Transaction Since

This section lists all the transactions of the interim account statement, which are supposed to be reported. You can choose the appropriate values applicable:

- MT942 - This indicates that all transactions posted and authorized since previous MT942 would be sent in the current interim statement.

- MT940 - This indicates that all transactions posted and authorized since previous MT940 will be sent in the current interim statement. If this option is selected, you will have to specify the cycle of account statement to be considered.
- MT941 - This indicates all transactions posted and authorized since the issue of a previous MT 941 in the current balance report

Interim Report Type

Select the interim report type from the adjoining drop-down list. This list displays the following values:

- Primary
- Secondary
- Tertiary

Minimum Debit Amount

Specify the minimum transaction amount for the debit transaction to be eligible for reporting in the interim statement. The corresponding amount for the account currency will be defaulted. However, you can modify the amount defaulted. If the amounts are not defined at the account class for the currency in which the account is being created, no defaulting of amounts shall be done.

Minimum Credit Amount

Specify the minimum transaction amount for the credit transaction to be eligible for reporting in the interim statement. However, you can modify the amount defaulted. If the amounts are not defined at the account class for the currency in which the account is being created, no defaulting of amounts shall be done.

Generate Balance Report

To indicate that the customer account is considered for generation of its balance message, check this box.

Report Transaction Since

This section lists all the transactions the customer account has undergone, in the interval of balance messages generated for the account. You can choose the appropriate values applicable:


- MT940: This indicates all transactions posted and authorized since the issue of a previous MT 940 in the current balance report
- MT941: This indicates all transactions posted and authorized since the issue of a previous MT 941 in the current balance report

Of


Select the mode of message for balance generation from the adjoining drop-down list. This list displays the following values:

- Primary
- Secondary
- Tertiary

2.2.19 Time Interim Transactions Report




2.2.20 Times – Balance Report



2.2.21 Specifying Notice Details

Notice preferences are maintained through the 'Notice Details' screen. Click the 'Notice'

button in the 'Islamic Account Class Maintenance' screen to invoke this screen.



The following field is displayed in this screen:

Description

The following details are defaulted from the account class maintenance level. However, at the account level you are allowed to modify this.

Advance Profit

Check this field to levy the advance profit on the account

Note

- The customer is liable to pay this advance profit in case he/she fails to provide the required notice to the bank
 - The system deducts the advance profit from the credit profit earned by the customer on his/her credit balance in the account
-

Monthly Free Amount

Specify the amount that the customer can withdraw per calendar month from his/her savings account without being liable to pay advance profit.

Notice Days

Specify the number of days before which the customer should notify the bank if he/she wants to withdraw an amount more than the 'Free Amount' from his/her account.

Validity Period


Specify the validity period in number of days. During this period, the customer can do the withdrawal of the amount for which he/she notified the bank.

Note

This screen is applicable only for saving type of account

2.2.22 Specifying Fields Details


User defined fields are maintained through the 'User Defined Fields' screen. Click the 'Fields' button in the 'Islamic Account Class Maintenance' screen to invoke this screen.



2.2.23 Triggering a Batch for Accounts Eligible for Profit Sharing

Based on the balance basis maintained in the 'Account Class Maintenance' screen and the transaction code-wise exclusion criteria maintained in the 'Exclusion Transaction Count' screen, the system will exclude all the accounts which satisfy the Exclusion criteria. You can trigger this Exclusion process through the 'Profit Calculation Exclusion Batch' screen. You can

invoke the 'Profit Calculation Exclusion Batch' screen by typing 'STDREXBT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.



You can enter the following details in this screen:

Period Code

Specify the period code for which you wish to run the batch process. The adjoining option list displays all the period codes maintained in the system. You can select the appropriate one.

Financial Year

Specify the financial year for which you wish to run the batch process. The adjoining option list displays all the financial year codes maintained in the system. You can select the appropriate one.

Click the 'Submit Batch' button to execute the batch. The system will identify all accounts that are not eligible for profit sharing in the given period and financial year and exclude them from the profit sharing computation process. The system will update the Mudarabah _Rate (UDE) as Zero with effective date as the start date of the period.

2.3 Maintaining Islamic Customer Accounts

You can define Islamic customer accounts for all the customers of your bank through the 'Islamic Customer Accounts Maintenance' screen.

Each Islamic deposit account that you define is identified with an account number. The structure of the account number is based on the account mask you have maintained through the Account Parameters sub-screen of the 'Bank-wide Parameters' screen.

The account number can be combination of the CIF Number, the Islamic account class, currency, and any other alphabet/s or number/s of the account or currency as defined.


For an account number, you also need to define (in this screen) other parameters like: the account class; the type of account - joint or single; the reporting lines for the account; the currency in which transactions can be passed to this account; the customer's account limit; the check book/passbook/ATM facility, the various statuses applicable to the account and so on.

Every Islamic account created or modified in Oracle FLEXCUBE needs to be authorized to become effective. Whenever a new customer account is created or an existing record is modified, the system generates a notification message on the record authorization. This notification message can be sent to any external system if required.

Note

You can query or modify the account details of the customers whose accounts are permitted to you for the query/modification in the 'Group Code Restriction' screen.

You can invoke the 'Islamic Customer Accounts Detailed' screen by typing 'IADCUSAC' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.



The details maintained in this screen have been classified into three broad heads:

| | |
|-----------|--|
| Main | Here you maintain the basic attributes of each customer account like the account number, customer code, the account class, account currency, type of account - single or joint, account status, other statuses applicable, Cheque Book preferences and so on |
| Auxiliary | Here you can view other details like provisioning and so on. |
| Nominee | Nominee details are maintained under nominee head |

The 'Islamic Customer Accounts Detailed Main' screen is displayed by default when you invoke the 'Islamic Customer Accounts Detailed' screen. The Branch Code of the sign-on branch is on display.

Branch Code

The system displays the branch code of the sign on branch.

Account

You can indicate the account number of the customer. One customer can have any number of accounts.

The structure of the account number is defined in the customer account mask maintained in the Account Parameters sub-screen of the Branch-wide parameters screen. The account number can be a combination of the account class, customer code (CIF Number), serial number or currency as defined in the customer account mask.

The last constituent of the account number is always a system generated check digit (it could be alphabetical or numeric depending upon the mask defined).

You cannot alter the relative position of the constituents of customer account (as defined in the mask) while maintaining actual customer accounts.

Currency

You have to identify the currency of the customer account. A list of all the currencies maintained in the system will be displayed in the available list. You can select the currency of transaction for the respective account. If the currency of the account is not defined for the current period in the 'Turnover Limit Maintenance' screen, you will not be able to save the account.

In case the account is linked to a fund, The system defaults the fund currency. You cannot modify this.

SD User Reference

The system displays the SD user reference for the TD accounts.

Customer No

If you have included the CIF Number of the customer as part of the Account Mask, the system automatically defaults the CIF code of the customer in the respective field. You can modify this code.

However, while defining the Account Mask in the Account Parameters section of the Bank-wide Parameters screen, if you have specified that the CIF Number should not be a part of the account mask you will have to specify the customer code manually. A list of all the valid customer codes is displayed in the available option list. You can select the appropriate.

Customer Name

On entering the Customer No, the customer name is automatically displayed.

Account Class

In Oracle FLEXCUBE, you can classify the customer accounts of your bank into different groups. Each group is referred to as an account class and is maintained in the Account Class Maintenance screen. For each class, you have to define certain common attributes applicable to all accounts in the particular class.

While maintaining a specific account you have to identify the class to which the particular account belongs. You can select the appropriate account class from the list of all the valid account classes maintained in the system. Account classes that have surpassed their end date (expired) will not be displayed in the option list.

2.3.1 **Main Tab**

The 'Main' tab is displayed, by default, in the 'Islamic Customer Accounts Detailed' screen. The fields in the Main section are as follows:

Description

This is the description of the account. Here you can enter the nature of the account like current, savings, overdraft, and so on. If a customer has two or more accounts under one account class you can specify the purpose of that account.

Account type

You have to indicate whether the account is to be opened only by the account holder or whether it can be jointly operated.

Fund Id

Select the fund id from the adjoining option list. The system defaults the value of Default Mudarabah Fund as fund id.

The system displays this field only in a case where the selected branch is a fund branch.

Country Code

To define the country limits for each individual country you have to select the country code from the option list available.

Mode of Operation

Indicate the mode of operation. Choose one of the following options from the drop-down list:

- Single
- Jointly
- Either-Any one or Survivor
- Former or Survivor
- Mandate Holder

Account Open Date

You have to capture the date on which the account was opened.

Alternate Account Number

You have to define an alternate account number for the account you are defining. The alternate account number that you specify should be unique for each customer. You can capture the old account numbers used by your bank before installing the Oracle FLEXCUBE system. The old account numbers would be mapped with the new account numbers. This would facilitate quick tracking of the account and generating queries.

In the Data Entry Module, you can input a transaction using the alternate account number instead of the actual account number.

Clearing Bank Code

The clearing bank code for the customer account is generated automatically if you have opted for auto generation in the Branch parameters

Clearing Account Number

The clearing account number for the customer account is generated automatically if you have opted for auto generation in the Branch parameters. The account number is created according to the account mask you have maintained for the branch. This will be mandatory, and has to comply with length of 9 characters and MOD 11 validation, if the value of the UDF 'Clearing A/C Mandatory' is maintained as YES in the Field Name to Value Definition screen.

However, you can choose to change this number here and the system validates this number with the account mask you have maintained for the branch

IBAN Account Number

To capture the detail of the IBAN account for a specific customer, you have to enable the 'IBAN Required' option by enabling it. Subsequently, click the 'M' button. The IBAN details sub-screen will be displayed.

In this screen, you can capture the IBAN Account Number as well as the bank code of the bank where the IBAN account resides.

Address

Specify the address of the customer.

Statuses

The status reflects the status of the account. The account may have a No Credit or No Debit order issued against it or a Stop Payment order or it may have been frozen for some reason and therefore dormant. While posting transactions to the customer account, the system checks the status of the account before the entry is processed

No Debits

No debits can be posted to the account. For example, Silas Marner, a customer of your bank, going abroad for a year instructs you not to debits his account till his return. You can execute this instruction by checking this box.

No Credits

No credits can be posted to the customer account by enabling the check box positioned next to this field

Stop Payments

For Stop Payments, if in the CASA module a stop payment instruction is issued (for a check or an amount) against the account number, the system automatically enables the 'Stop Payment' check box. When the stop payment instruction is withdrawn, the status gets updated accordingly. If a customer has requested for stop payment of multiple cheques, the 'Stop Payment' option will continue to remain checked till the last request is also cancelled. After cancellation of the last stop payment instruction, the option gets updated (unchecked) immediately

Dormant

The system updates this status for an account based on the dormancy days specified in the 'Account Class Maintenance' screen.

Frozen

If you have frozen a customer account in the 'Customer Information Maintenance – Basic' screen the accounts gets frozen. For instance, at the behest of a court order, the status of the account is reflected here in the 'Customer Accounts Maintenance' screen.

Posting Allowed

If checked, indicates that the account class being created is to be used while creating IRA monetary accounts. Monetary accounts used for IRA need to be distinguished from the other accounts in Oracle FLEXCUBE, so that these accounts do not come up for posting in the other Oracle FLEXCUBE screens.

Status Change Automatic

This specification will be defaulted from the account class to which the account belongs. However, you have the option of changing it at the customer account level. If you check this option, the status of the account will be changed automatically by the system as per the

conditions maintained in the 'Status Rule Definition' screen (invoked from the Account Class Maintenance screen). If you do not select this option, you have to change the status manually through the 'Manual Status Change' screen.

OverDraft

Check this option to provide overdraft facility for the account.

Refer to the section titled 'Modifying an account status manually' later in this chapter for more details.

Contribute to PDM

This box is checked by default while creating an account, to indicate that the account balance should be considered for contribution to the profit distribution pool. However, you can uncheck it.

Exclude from Distribution

This preference is defaulted from the linked account class. However, you can change it.

If this box is checked, the system will not consider the account for profit distribution. Leave the box unchecked to include the account in profit distribution. Note that you can uncheck this box only if you check the box 'Contribute to PDM'.

Note the following:

- If you check the box 'Contribute to PDM' and uncheck the box 'Exclude from Distribution', the system will consider the account balance as the depositor's contribution and also distribute profit to the depositor.
- If you check the boxes 'Contribute to PDM' and 'Exclude from Distribution', the system will consider the account balance as the depositor's contribution but it will not distribute profit to the depositor.

Account Set for Closing

On receipt of the closure request for the account wherein profit distribution is due, you can check this box after making the account balance '0' and then pay the customer. If a transaction is initiated on an account for which this box is checked, the system will display the override message as, "Account set for closure do you wish to still process?"

If you select 'OK', the system will allow you to proceed with the transaction. This override will be displayed only if the transaction is initiated using any module other than the Funds transfer module. In case of a transaction initiated through the FT module on an account for which this box is checked, the system will display an error message.

Note the following:

- You can check this box only for Savings and Current type of account.
- Once you check this box and save the record, you will not be able to uncheck it.
- Upon re-opening the account, the system will automatically uncheck this box.

Closing Date

The system displays the date on which you have checked the box 'Account Set for Closing'. This date is used to validate the profit sharing cycle settlement in order to close the account automatically.

NSF Blacklist Status (Non Sufficient Fund)

NSF Blacklist Status indicates that the customer account is blacklisted due to NSF rejection.

If cheque is rejected or returned due to NSF, the blacklisted formula is executed to get the new NSF level of the customer. If the new NSF level is a blacklisted level, then the customer

account will be marked as a blacklisted and check book facility of all the customer's accounts will be revoked.

In case the new NSF level is not a blacklisted level, then the customer is marked as a non-blacklisted customer and check book facility will be enabled for that customer account.

For Joint account:

- If cheque is rejected due to NSF in a joint account, all of the customer's NSF level is changed from Level 1 to Level 2 and so on.
- Corporate or individual accounts:
- If the blacklisted customer, is an authorized signatory in a corporate account, then the corporate account will not be frozen.
- If a corporate customer is blacklisted due to cheque return, then the authorized signatories are not blacklisted and their individual accounts will not be blacklisted.

Note

NSF blacklist status is an indicator in the account to indicate the blacklist status. System will continue to support the credit or debit transaction of the account.

Status Details

Specify the following details.

Status

At the time of maintaining a customer account for the first time, the account status will be 'NORM' (Normal) by default. The 'Status Since' field will display the current system date, that is, the date on which the account is maintained in the system. The system will update the status whenever a status change occurs. Therefore, at any point of time, this field will display the current status of the account. The 'Since' field will reflect the date on which the account moves to the current status.

Subsequently, the system will default the value of CIF Status as available in the 'Customer Maintenance' screen. This status is the worst status among all the finances, savings accounts and current accounts for the customer in the current branch.

Note

This is done if you have opted for status processing at the 'Group/CIF' level as part of your branch preferences.

Since

The date on which the status of the account is changed to the current status is displayed here

Propagate Reporting Details

This field indicates whether the reporting lines defined for status movement, for the account class that this account reports to, must also be applicable to it.

The following GL's are defined in the Account Class Maintenance for posting account balances when a status movement occurs on any accounts belonging to the account class:

- The Debit and Credit GL's to which account balances must be posted, for movement to each status
- The Central Bank Reporting Debit and Credit GL's

- Head Office Reporting Debit and Credit GL's

When you select this option, the GL's maintained for the account class will be applicable to the customer account you are defining in this screen. The reporting lines will be propagated to the account whenever a status change occurs.

If you do not want the account class details to be propagated to the account as well, you have the option of maintaining the status codes and the reporting lines exclusively for an account. You can achieve this through the 'Status Details' screen. Click the 'Account Status' button in the 'Islamic Customer Accounts Detailed' screen to invoke it.

Account Auto Closed

The system checks this option to identify the accounts that should be closed by auto account closure. By default the system will not check this option.

Account Derived Status

The system displays the current status of the account here. This is applicable for CASA accounts (current accounts and savings accounts).

Dormancy Parameters

If Transaction Code associated with the account has the consider for account activity option enabled, the dormant status of the account will be updated to active. Apart from this, you can specify the parameter that is required for re-activating the account. Choose from the following options to indicate the re-activation parameters for the dormant account.

- Debit
- Credit
- Any
- Manual

In case of a transaction, the system will check for the parameter you have specified here and accordingly change the status of the account. The parameter you specify here will supercede the parameter you have maintained at the account class level.

Location

An address for a customer account is based on the 'Location' and 'Media' combination. Location codes maintained through the 'Account Address Location Type Maintenance' screen are made available against this field. The address maintained here is always the primary or the default address. Each customer can have several addresses for a particular media. To distinguish between one address of a customer from another for a given media, it is essential for you to specify a unique location for each address. Also, if you are amending an address here, the same gets updated in the 'Customer Account Address - Detailed' table after the validations are through.

Media

Indicate the media for which the charge should be levied. Select one of the following options from the option list:

- Mail
- Telex
- SWIFT
- Fax

Linked Deposit Branch

This field displays the branch of the account that is linked to both the funds when the inter-fund subscription happens. This field is updated by the system when inter-fund subscription transaction is booked.

Linked Deposit Account

The system updates this field in case of an inter-fund subscription.

If an Islamic deposit account is linked to a fund, the system verifies if there exists a parent account for the child deposit. It also verifies whether the parent account class is maintained in the fund online. If the parent account does not exist, the system displays an error message.

You cannot close a parent account unless all child accounts are inactive. However, you can create multiple parent accounts for same fund and customer combination.

Zakat Exemption

When an account is opened in a branch, you need to clarify with the customer whether he or she will pay *Zakat* or will seek exemption. Check this box to indicate that the customer seeks exemption from *Zakat* charge.

Options

Track Receivable

During liquidation of finance contracts as well as processing of retail teller contracts, if the system detects insufficient funds in the settlement account, then you can choose to block the subsequent credit that happens to the settlement account. In other words, the system will track the account for receivables (credits). As and when a credit happens, the funds will be allocated to the finance or retail teller contract, for liquidation. If the track receivable option is checked for the account, the system will track the receivables for the account if sufficient funds are not available in the account.

The allocation of funds will happen in a sequence that you specify at the account class level. This is explained in the section titled 'Maintaining Account Classes'.

Referral Required

Referral refers to the process of handling customer transactions, which force the accounts involved in such a transaction to exceed the overdraft limit. Examples of typical transactions, which force an account to move into overdraft, are Payment and Collections, Funds Transfers, Standing Instructions or Clearing transactions. The 'Referral Required' option is defaulted from the account class linked to the account. However, you can change it for a specific account. If an account is marked for referral, the details of transactions resulting in the account moving into Overdraft will be sent to the referral queue.

IBAN Required

Check this box to indicate whether you required IBAN or not.

Replicate Customer Signature

The signature of the customer gets defaulted from the account class level to account level. This value is defaulted only if the customer type is individual with single mode of operation.

Salary Account

Check this option to indicate the salary account which should be selected for finance recovery on salary credit. By default this option is unchecked.

Turnover Limit Preferences

Turnover Limit Code

The system displays the turnover limit code applicable to the account.

2.3.2 Auxiliary Tab

Click 'Auxiliary' tab in the 'Islamic Customer Accounts Detailed' screen. The fields in the Auxiliary section are as follows:

The screenshot shows the 'Islamic Customer Accounts Detailed' application window with the 'Auxiliary' tab selected. The interface is divided into several sections for configuring account settings:

- Header Fields:** Branch, Account, Currency, SD User Reference, Customer No, Customer Name, and Account Class.
- Positive Pay:** Includes checkboxes for Positive Pay, Funding, Mod 9 Validation Required, and Deferred Reconciliation. It also has fields for Stale Days, Fund Branch, Funding Account, and Validation Digit.
- Provisioning Details:** Includes Exposure Category, Risk Free Exposure Amount, Provisioning Currency (Account/Local/Provision), and Auto Provisioning Required.
- Cheque Book Preferences:** Includes Auto Reorder of Cheque Book, Reorder Cheque Level, Reorder No of Leaves, Cheque Book Name 1, Cheque Book Name 2, and Max No of Cheque Rejections.
- Account Facilities:** Includes checkboxes for Cheque Book, Passbook, and CAS Account.
- Options:** Includes checkboxes for Euro Cheques, MT210 Required, Lodgment Book, Consolidated Certificate Required, Back Period Entry Allowed, Default Waiver, Mudrabah Sweep, Auto Deposit, Auto Cheque Book Request, and Auto Debit Card Request.
- ATM Details:** Includes ATM, Branch, ATM Account Number, Daily Amount Limit, and Daily count Limit.
- Intermediary Details:** Includes Intermediary Required and an 'Intermediate' table with columns for Intermediary Code and Intermediary Description.
- Initial Funding:** Includes Account Opening Amount, Pay In Option (Pay In By Account/Pay In By GL), Offset Branch, Offset Account, and Waive account Opening Charges.
- Escrow Transfer Details:** Includes Escrow Transfer Applicable, Branch Code, Escrow Account, and Escrow Percentage.
- Passbook Details:** Includes Passbook Number and Passbook Status.

The bottom of the screen features a navigation bar with various menu items and a status bar with fields for Maker, Checker, Date Time, Mod No, Record Status, and Authorization Status, along with an Exit button.

Positive Pay

Indicate the following:

Positive Pay

For the account you are maintaining, you can specify whether you want positive pay facility for the account or not. When a check comes in for payment, the system validates for any unpaid record only for those accounts that are under positive pay. For all the other accounts that are not specified for positive pay, the system does not do any validation before making payments for the checks.

Funding

If you enable 'Funding', accounting entries will be posted by the Positive Pay maintenance/upload table for the positive pay transaction. You have to enable 'Positive Pay' to make use of 'Funding' functionality. If 'Positive Pay' is not enabled, 'Funding' option will not be applicable.

If 'Funding' is not selected, accounting entries will not be passed for positive pay transactions.

Note

You cannot enable both 'Deferred Reconciliation' and 'Funding' functionalities. You have to choose between either of them for a particular account.

Mod 9 Validation Required

You can enable Mod 9 Validation for positive pay accounts only. Only if positive pay enabled then Mod 9 Validation will be active.

In the case of inward clearing of Positive Pay files, if Modulo 9 is enabled for the product, the system performs a Modulo 9 Validation on any new cheque. If the cheque fails modulo 9 validations the system will display an error message on save. In case of check replacement the Modulo 9 Validation is done for the new check number while in case of alphanumeric checks, the system throws an error message if modulo 9 validation is checked.

When uploading a positive pay cheque the system will perform a Modulo 9 Validation if Modulo 9 validation is enabled for the product. If the validation fails, this particular check will not be uploaded. The same will be valid in case of Cheque Replacement while for alphanumeric checks, system will skip the check and display an error.

Stale Days

If you have specified a positive pay facility for the account you are maintaining, then you have to indicate the number of stale days for the transaction. If the date of processing happens after the specified stale date then the transaction gives an exception error. You have to do an override for this exception.

Fund Branch

Click on the adjoining option list to choose from the list of branches maintained. The positive pay parking account will be picked from this branch.

Deferred Reconciliation

Enabling this check box indicates whether or not the Positive Pay account has the Deferred Reconciliation facility. Deferred Reconciliation is the facility wherein a Positive pay cheque which is free of any disparity is cleared by the bank even in the absence of any instruction from the drawer of the cheque. The instruction can be deferred.

Deferred Reconciliation function goes hand-in-hand with the Positive Pay described above and Deferred Reconciliation is applicable only for Positive Pay Accounts

- If Positive Pay = No and Deferred Reconciliation = No, the cheque is subjected to the usual validations and is Rejected if:
 - There is any discrepancy in the instrument.
 - There is a Stop payment instruction issued against the instrument
- If Positive Pay = Yes and Deferred Reconciliation = No, Cheque is subject to the usual validations and processing.
- If Positive Pay = Yes and Deferred Reconciliation = Yes, and if any one or more of the three fields viz. Branch, Account No., Cheque No., does not match with the Positive Pay instruction, the cheque will be put under Deferred Reconciliation as Unreconciled

- If this unreconciled cheque comes in for clearing once again with the same set of parameters, it is Rejected.
- If Positive Pay instruction is received for an unreconciled cheque, it is marked Reconciled and the cheque status is marked Liquidated.
- If Positive Pay = Yes and Deferred Reconciliation = Yes, and the Amount field does not match with the Positive Pay instruction, the check is Rejected outright.

All data pertaining to reconciled and unreconciled cheques are maintained and information regarding account no., cheque no., amount and status of the instrument [reconciled or unreconciled] can be retrieved if needed.

An EOD batch function will purge all reconciled cheques as part of the clearing batch process.

During the upload process, validation is done against all the positive pay and the deferred reconciliation flags combinations and all Unreconciled Positive Pay Instructions are marked as Reconciled and liquidated.

Deferred reconciliation will be overridden by a stop payment instruction if any. An error message (or an override) will be shown if a Cheque that comes in for clearing has a stop pay instruction against it but has no positive pay instruction.

Funding Account

Click on the adjoining option list to choose the account into which funds have to be transferred on receipt of a positive pay instruction. The accounts that satisfy the following conditions will be available in the list of 'Positive Pay Parking Account':

- Both accounts belong to the same customer
- The currency of both the accounts is the same

Validation Digit

Validation digit will be having values only 0 and 9. If validation digit is 9, then $9 - \text{mod } 9$ remainder for the check number (Excluding the check digit) should be equal to the check digit for the check to be passed else the check is rejected.

The check digit is the last digits of the check, that is, if check number is 1800 then check digit is 0. The mod 9 remainder of the check number should be equal to the check digit for the check to be passed if validation digit in customer accounts maintenance is 0 else the check is rejected.

Account Facilities

Specify the following:

Cheque Book

Enabling this check box indicates whether or not the accounts linked to the class are issued checkbooks.

Passbook

Enabling this check box indicates whether or not the accounts linked to the account class are issued passbooks.

CAS Account

Specify CAS account.

Offset Branch

Choose the branch ID for the offset account, specified in the next field, from the option list.

Offset Account

You have to specify the customer account from which the money is to be debited for booking the TD. If you click on option list in the Offset Account field, a list of all valid account numbers that is maintained in the branch (specified in the previous field) will be displayed. Double click on the account that you want to specify as the offset account.

Waive Account Opening Charges

Check this box to indicate that account opening charges should be waived for individual customer account.

Auto Cheque Book Request

Check this box if you want the system to create request for the cheque book automatically, for the account during account creation.

When you check this box, the system allows you to capture cheque book request details in the Cheque Book Request screen, as part of account creation.

Auto Debit Card Request

Check this box if you want the system to create request for the debit card automatically, for the account during account creation.

When you check this box, the system allows you to capture debit card request details in the Debit Card Request Details screen, as part of account creation.

Provisioning Details

Auto Provisioning Required

You can indicate whether provisioning is applicable for the account. If you indicate so, the provisioning batch, when executed, picks up the account for provisioning.

Exposure Category

If the logic for deriving the exposure category of the CIF or customer group to which the customer belongs, based on the total exposure, has been maintained in the Exposure Type Category Linkage maintenance, then the exposure category of the account is identified. If no logic has been maintained, you can specify the exposure category in the 'Islamic Customer Account Maintenance' screen.

Risk Free Exposure Amount

You can indicate the risk-free exposure amount that would be used in computing the provisioning amount for the account.

Provisioning Currency

You can indicate the currency in which the provisioning amount must be calculated – either account currency or local currency. This specification is defaulted from the preferences for the Islamic account class used by the account, and you can alter it if necessary.

Options

Indicate the following:

Euro Cheques

Euro chequebook can be issued to a customer whose account has checked for 'Euro cheques' option in the customer account maintenance screen the account should be a account with EUR currency only.

Mt210 Required

A Notice to Receive message (MT210) is an advance notification to your account servicing institution that it will be receiving funds that are to be credited to your bank's account with that institution.

For a nostro account, you can specify whether the nostro agent (your account servicing institution) prefers to receive a Notice to Receive SWIFT message (i.e., MT 210) when it is debited in the case of a funds transfer. To indicate that the message MT 210 is to be generated by default whenever the nostro account is the debit account for a funds transfer, select the 'MT 210 Required?' checkbox in the Customer Accounts Maintenance screen, for the relevant nostro account.

If you indicate so, an MT 210 is generated by default whenever this nostro account is being debited during the posting of accounting entries in any transaction. This preference (to generate an MT 210 by default) can be over-ridden when you enter a contract involving a debit to the nostro account.

Once you have specified this preference for a nostro account, you can change it whenever necessary. For instance, if you have not specified that an MT 210 be generated, you can unlock the record and specify the generation of MT 210. Conversely, if you have specified that MT 210 generation is applicable, you can unlock the record and specify that it is no longer applicable.

Lodgment Book

If you wish to allow orders of lodgment books for all accounts that use this account class, you can indicate so, in the 'Islamic Customer Accounts Detailed' screen, by selecting the Lodgment Book option.

Consolidated Cert. Reqd.

Check this box if you required consolidated certificate.

Back Period Entry Allowed

You can choose to allow the posting of back-valued entries into the account by enabling the Back Period Entry Allowed option. If you choose not to restrict back period entries, you will be allowed to post journal entry transactions to past periods as long as the account is open.

This specification is defaulted from the Islamic account class linked to the account. You can choose to change it for a specific account.

Note

While posting back-valued transactions, the System verifies whether the Back Period Entry Allowed option has been enabled for the account. If the option has not been enabled an error message is displayed. This check is also performed while uploading journal entry transactions.

Mudarabah Sweep

Check this box to opt for Mudarabah sweep.

This can be checked only if Overdraft is enabled at account class level.

If Mudarabah Sweep is not checked and if linked deposit details are given for an account then the system displays an error message as, "Linked deposit details can be given only if the flag 'Mudrabah sweep' is checked"

Auto Deposit

Check this box to indicate that deposit will be created automatically for the account for auto deposit.

Note

If auto deposit is checked and if the deposit instructions are given for the account then the system automatically creates deposit whenever the credit balance in the account crosses the minimum required balance.

ATM Details

Specify the following:

ATM

Enabling this check box indicates whether or not the accounts linked to the class will avail the ATM facility.

Branch

Specify the branch at which the Islamic deposit customer is having the account.

Account Number

You can indicate the account number of the Islamic deposit customer. One customer can have any number of accounts.

The structure of the account number is defined in the customer account mask maintained in the Account Parameters sub-screen of the Branch-wide parameters screen. The account number can be a combination of the account class, customer code (CIF Number), serial number or currency as defined in the customer account mask.

The last constituent of the account number is always a system generated check digit (it could be alphabetical or numeric depending upon the mask defined).

Note

You cannot alter the relative position of the constituents of customer account (as defined in the mask) while maintaining actual customer accounts.

Daily Amount Limit

Specify the daily limit for the amount that can be withdrawn from the ATM.

Daily Count Limit

Specify the daily count for the amount that can be withdrawn from the ATM.

Cheque Book Preferences

In Oracle FLEXCUBE, you can set off automatic reordering of Cheque Books for a Islamic account. You can set up parameters based on which the system will trigger this activity. The Cheque Book preferences maintained for the Islamic Account Class, to which the account belongs, will be defaulted to this screen. However, you may change your specifications for an account, if required.

Auto Reorder of Cheque Book

You have to select this option to specify that automatic reordering of Cheque Books is required for the account being maintained. This option will be enabled only if you have indicated that the account holder should be provided with a Cheque Book facility.

The automatic reordering of Cheque Books is processed at EOD by executing a batch function. The following conditions should be satisfied for initiation of automatic reordering:

- The 'Auto Reorder of Cheque Book' option is turned on at the account level
- The number of unused check leaves for the account is less than or equal to the reorder level maintained at the account level. The system will pick up the number of leaves to be reordered from the field 'Reorder Number of Leaves' maintained for the account.

The numbering of cheque leaves for the new Cheque Book will depend on the 'Cheque Number Unique for Branch' option in the 'Bank Parameters' screen. If this option is checked, the numbering will begin from the Last Number + 1 of the Cheque Book that was delivered last to *any account*. If you do not select this option, the number will start from the Last Number +1 of the Cheque Book delivered to the same account previously.

The value of 'Include for Cheque Book Printing' and 'Cheque Type' (specifications defined in the 'Cheque Book Details' screen) will be defaulted from the previous order of the Cheque Book.

Reorder Cheque Level

Here, you have to indicate the level at which the reordering of Cheque Book should happen. Automatic reordering will be set off by the system when the unused number of cheque leaves becomes equal to or less than the re-order level that you maintain here. This field will be enabled only if you have indicated that automatic reordering of Cheque Books is required, that is, the 'Auto Reorder of Cheque Book' option is checked.

Reorder Number of Leaves

Specify the number of leaves that should be ordered for the new Cheque Book. This field will be enabled only if you have checked the 'Auto Reorder of Cheque Book' option earlier.

Cheque Book Name 1

Specify the name used for opening savings account A1. This name will be printed on the cheque book and will be used for all cheque transactions.

Cheque Book Name 2

Specify the name if you need to enter the name of the joint account holder on the cheque book, if the customer account is joint operations account.

Max No of Cheque Rejection

The system defaults the value of maximum number of cheque rejections that can be allowed for an account from the account class. However, you can modify it at the account level.

Initial Funding

Account Opening Amount

Specify the amount being deposited to open a customer account. While saving the record, the system checks whether this amount is equal to or greater than the minimum limit maintained for the linked account class. If the amount is less than the applicable limit, the system will display an error message. If it is equal to or greater than the limit amount, the system will proceed with saving.

Input to this field will be mandatory if limit amount has been maintained for the linked account class.

Pay-in Option

Indicate the method for initial funding during account creation. Choose one of the following options:

- Pay In By Account

- Pay In By GL

Escrow Transfer Details

Specify the following details.

Escrow Transfer Applicable

This box is checked by default if the customer account belongs to an account class for which Escrow transfer is enabled.

Note

This box should be checked for Project/Trusted account(s) only.

Branch Code

Select the branch code in which the Escrow account has to be created from the adjoining option-list.

Escrow Account

Select a valid account to be used as an Escrow account from the adjoining option-list. The list displays all valid accounts based on the selected Escrow branch and the currency of the project account.

Escrow Percentage

Specify the percentage of the credited amount, which has to be transferred to the Escrow account.

Note

The Escrow percentage specified here will be same for all transactions and will not vary for different credits like cash, cheque, draft etc.

Passbook Details

System displays the passbook details here.

Passbook Number

The system displays the passbook reference number. You cannot modify the value

Passbook Status

The system displays the current status of the passbook. You cannot modify the value

Note

Passbook details get populated once the passbook is issued for the customer account with the latest status and latest passbook number issued.

2.3.3 Nominee Tab

The screenshot shows the 'Islamic Customer Accounts Detailed' window. At the top, there are search and navigation options: 'New' and 'Enter Query'. Below this, there are several input fields for account identification: 'Branch *', 'Account *', 'Currency *', 'SD User Reference', 'Customer No *', 'Customer Name', and 'Account Class *'. A tabbed interface is visible with 'Main', 'Auxiliary', 'Nominee', and 'Check List' tabs. The 'Nominee' tab is active, showing 'Nominee Details' with a '1 Of 1' indicator. The details section includes fields for 'Name', 'Date of Birth', 'Relationship', 'Address 1', 'Address 2', 'Address 3', 'Address 4', 'Guardian Name', 'Relationship', 'Address 1', 'Address 2', 'Address 3', and 'Address 4'. There is also a 'Minor' checkbox. At the bottom of the window, there is a navigation bar with various menu items like 'Profit', 'Charges', 'Consolidated Charges', etc., and a status bar with fields for 'Maker', 'Checker', 'Date Time', 'Mod No', 'Record Status', and 'Authorization Status', along with an 'Exit' button.

Click 'Nominee' tab in the 'Islamic Customer Accounts Detailed' screen. The fields in the Nominee section are as follows:

Nominee Details

Name

Specify the name of the nominee.

Date of Birth

Specify the date of birth of the nominee.

Relationship

Specify the customer's relationship with the nominee.

Address 1, 2, 3 and 4

Specify the address of address of the nominee. Four lines have been provided for this. Each line can have a maximum of 35 characters, alphanumeric.

Minor

Check this option to indicate that the nominee is a minor.

Guardian Name

Specify the name of the guardian of the nominee if the nominee is a minor. You can capture the name of the legal guardian, not exceeding 35 characters, alphanumeric.

Relationship

Specify the nominee's relationship with the guardian.

Address 1, 2, 3 and 4

Specify the address of address of the guardian. Four lines have been provided for this. Each line can have a maximum of 35 characters, alphanumeric.

2.3.4 Check List Tab

Click 'Check List' tab on the 'Islamic Customer Accounts Detailed' screen. The following screen will be displayed.

The screenshot displays the 'Islamic Customer Accounts Detailed' application window. At the top, there are input fields for 'Branch *', 'Account *', 'Currency *', 'SD User Reference', 'Customer No *', 'Customer Name', and 'Account Class *'. Below these is a tabbed interface with 'Main', 'Auxiliary', 'Nominee', and 'Check List' tabs. The 'Check List' tab is active, showing a 'Document List' table with columns: Document Type, Mandatory, Expiry Date, and Expected Date of Submission. Below the table are 'Unload', 'Delete', and 'View' buttons. The 'Document Notification Details' section includes a 'Send Notification' checkbox, a 'Frequency' dropdown menu, and a 'Days' input field. The 'Remarks' section has two text areas. The bottom of the screen features a navigation menu with links like 'Profit', 'Charges', 'Consolidated Charges', etc., and user information fields for 'Maker', 'Checker', 'Date Time', 'Mod No', 'Record Status', and 'Authorization Status', along with an 'Exit' button.

Specify the following details:

Document Type

Specify the document type. The adjoining option list displays all the document types that are maintained in the system. You can select the appropriate one.

Mandatory

Check this box to indicate that the document specified here is mandatory.

Expiry Date

Specify the expiry date of the document provided by the customer.

Note

- Expiry date will always be greater than 'Expected Date of Submission' and 'Actual Submission Date'.
 - Expected Date of Submission will always be greater than current date.
-

Expected Date of Submission

System displays the expected date on which the customer is accepted to submit the required documents.

Actual Submission Date

System displays the actual date on which the customer has submitted the required documents.

Document Reference

System defaults the document reference here.

Checked

Check this box to indicate that the received documents are acknowledged.

Note

You cannot save and authorize an account if the mandatory documents are not confirmed as 'Checked'.

Upload

Click on this button to upload the selected document type.

Delete

Click on this button to delete the selected document.

View

Click on this button to view the selected document.

Notification Details

System defaults notification details from the 'Account Class Maintenance' screen.

Send Notification

This check box indicates whether to send notifications or reminders for not submitting the mandatory documents.

Frequency (Notification)

System defaults the frequency of notification to be sent. The frequency can be one of the following:

- Daily
- Weekly
- Monthly
- Quarterly
- Half yearly
- Yearly

Note

Notification will be sent only if,

- The check box 'Send Notification' is checked in Account Class Maintenance' screen.
- The account status is active and authorized.
- The mandatory documents are not submitted.

Notifications will be sent based on the frequency specified.

First notification will be sent on the expected date of submission or expiry date

If notification date falls on a holiday then system will send the notification on next working day.

Days (Reminder)

System defaults the number of days left for the expiry or submission due date of the documents for sending the reminder.

System will send the following reminders:

- Reminder prior to the submission due date of the document.
- Reminder prior to the expiry date of the document.
- Overdue notifications after the due date if the document is not submitted based on the frequency.
- Notifications after the expiry date if the document is not submitted after the expiry date.

Note

Reminder will be sent only if,

- The mandatory documents are not submitted.
- The account status is active and authorized.

Reminder will be sent only once.

If reminder date falls on a holiday then system will send the notification on next working day.

Reminder will be sent prior the number of days specified at the account level from expected date of submission or the expiry date.

If there are more than one notifications or reminders of the same message type for which the notification schedule date falls on the same day for the same account, a single notification will be sent which will have the details of all the related documents.

Remarks 1 to 10

Specify the additional information, if required.

2.3.5 Capturing Additional Details

You can capture additional details for the Islamic Customer Accounts by clicking the following buttons in the 'Islamic Customer Accounts Maintenance' screen:

| Button | Function |
|----------------------|---|
| Profit | This invokes the 'IP Special Conditions Maintenance' screen. |
| Charges | This invokes the 'Account level Charges Condition' screen. |
| Consolidated Charges | This invokes the 'Account level Consolidated Charges Condition' screen. |
| BIC | This invokes the 'Authorised SWIFT BICs for Customer Account' screen. |
| Deposits | This invokes the 'Deposits' screen. |

| | |
|-----------------------------|---|
| Instructions | This invokes the 'Account Operating Instructions Maintenance' screen. |
| Standing Instructions | This invokes the 'Instruction Diary Summary' screen. |
| Linked Entities | This invokes the 'Linked Entities' screen. |
| REG | This invokes the 'REG Details' screen. |
| Account Status | This invokes the 'Status Details' screen. |
| Restrictions | This invokes the 'Products and Transaction Codes Restriction' screen. |
| Currency Limits | This invokes the 'Currency Limits Details' screen. |
| MIS | This invokes the 'Management Information System' screen. |
| Statement | This invokes the 'Statement Details' screen. |
| Limits | This invokes the 'Account – Limits' screen. |
| Joint Holders | This invokes the 'Joint Holders' screen. |
| Fields | This invokes the 'User Defined Fields' screen. |
| Deposit Instruction | This invokes the 'Deposits Instruction' screen. |
| Billing Parameters | This invokes the 'Billing Parameters' screen. |
| Account Signatory | This invokes the 'Signatory Details' screen. |
| Interim Transactions Report | This invokes the 'Interim Transactions Report' screen. |
| Notice | This invokes the 'Notice Preference' screen. |
| Cards | This invokes the 'Cards Summary screen' screen. |
| OFAC Check | This invokes the 'External System Details' screen. |

| | |
|------------|---------------------------------|
| Change Log | This invokes the 'View' screen. |
|------------|---------------------------------|

2.3.6 Specifying Profit Details

You can capture details of special condition for the account, using the 'IP Special conditions Maintenance' screen. To invoke this screen, click the 'Profit' button in the 'Islamic Customer Accounts Detailed' screen.

The following details are captured here:

Branch Code

The current branch code is defaulted here.

Calculation Account

Select the valid customer account number for calculation from the adjoining option list.

Profit Booking Account

Select the valid customer account number from the adjoining option list.

Charge Booking Account

Select the valid customer account number for booking the charge from the adjoining option list.

Profit Statement

Check this box to generate the profit statement.

Consolidated Charge Account

Select the valid account number from the adjoining option list.

Profit Start Date

Select to indicate the effective date to generate profit from the adjoining calendar.

Charge Start Date

Specify to indicate the effective date to generate charges from the adjoining calendar.

Profit Booking Branch

Select to indicate valid Branch for calculating the profit from the adjoining option list.

Cr Advices

Check this box to generate credit related advices.

Charge Booking Branch

Select to indicate the valid Branch from the option list, for calculating the charge.

Consolidated charge branch

Select the valid branch from the adjoining option list.

Product Details

You can specify product details for your account here.

Product Code

Select the valid product code from the adjoining option list. The option list displays the products maintained at 'Islamic Profit Distribution Maintenance Detail' level.

UDE Currency

The system generates the user defined currency type maintained at 'Profit Product Preference' level.

Integrated LM Product

Select this option to indicate that Integrated Liquidity Management is applicable to the customer.

IL Product Type

Specify the IL product type.

Waive Profit

Check this box if you need to waive of profit or charges defined for the selected profit product at the Profit Product Preference level.

Generate UDE Change Advice

Check this box if you need to generate advice for user defined changes for the account.

Open

Check this box if you need to apply the selected profit product for the account.

UDE Values

Variance

Specify the variance in the profit rate. This is the variance alone. The effective rate will be the sum of the IC rate code and the variance that you specify here. This value can be modified at anytime.

2.3.7 Specifying Charges Details

You can capture details of charges for the account, using the 'Account level charges conditions' screen. To invoke this screen, click the 'Charge' button in the 'Islamic Customer Accounts Detailed' screen.

The screenshot shows the 'Account level charges conditions' window. It features a blue title bar with a diamond icon and window controls. The main content area is divided into three sections: 'Account Details' with 'Branch' and 'Account' text boxes and a 'Default' button; 'Product Details' with 'Product Code *', 'Description', and 'Currency' text boxes, and 'Minimum', 'Maximum', and 'Free Items' text boxes, plus 'Waive Charges' and 'Open' checkboxes; and 'List of Slab Amounts' which is a table with columns for 'Slab Amount *', 'Charge Amount', and 'Rate'. The table is currently empty. The bottom of the window has a blue bar with 'Ok' and 'Exit' buttons.

You can enter the following details:

Branch

The Branch Code to which the account belongs (for which you are defining special conditions) is displayed in this field.

Account

The Account number of customer (for which you are defining special conditions) is displayed in this field.

Note

You can click the 'Default' button to default the Charge Products and the corresponding details applicable for the account. You can then modify these values to define the special conditions.

Specifying Product Details

Specify the following details:

Product

The system defaults a product when you click the 'Default' button at the time of account creation. You must modify it to identify the Charge product using which the applicable charges would be collected.

Currency

The charges would be collected in the currency defined for the selected charge product, and this currency is displayed on the screen.

Minimum and Maximum

You must indicate the charge amount range, representing the minimum and maximum charge that can be applied for the account.

Free Items

You must indicate the number of free items for which the customer will not be charged.

Open

By default, each charge consolidation charge set-up that you set up is enabled and active. You can also disable the set-up by checking the 'Open' box. If the account is marked for closure, you will have to uncheck this box.

Waive Charges

You can choose to waive charges for an account.

2.3.8 Specifying Consolidated Charges Details

Consolidated Charges are maintained through the 'Account level Consolidated Charges Condition' screen. Click the 'Consolidated Charges' button in the 'Islamic Customer Accounts Detailed' screen to invoke this screen.

The screenshot shows a software window titled "Account Level Consolidated Charges Conditions". The window is organized into three main sections:

- Account Details:** Contains two input fields: "Branch Code" and "Account".
- Product Details:** Contains four input fields: "Product Code", "Currency", "Minimum", and "Maximum". To the right of these fields are two checkboxes: "Waive Charges" and "Open". A "1 Of 1" indicator is present on the right side of this section.
- Discount:** Contains two input fields: "Discount Percentage" and "Discount Amount".

At the bottom right of the window, there are two buttons: "Ok" and "Exit".

Account Details

You can maintain the account details for an account here.

Branch Code

The current branch code is defaulted here.

Account

The system generates the account number maintained in the 'Main' screen of 'Account Class Transfer'.

Product Details

You can specify product details for your account here.

Product Code

Select a valid product code from the adjoining option list.

Currency

The system generates the user defined currency type defined for the selected consolidated charges product.

Minimum

Specify the minimum consolidated charges that can be applied for the account.

Maximum

Specify the maximum consolidated charges that can be applied for the account.

Open

Check this box if you need to apply the selected consolidated charges product for the account.

Waive Charges

Check this box if you need to waive the consolidated charges defined for the selected consolidated charges product.

Discount

You can specify discount details for the consolidated charges applied for the account.

Discount Percentage

Specify percentage of the amount to be discounted from the computed consolidated charges.

Discount Amount

Specify a flat amount to be discounted from the computed consolidated charges.

2.3.9 Specifying BIC Details

You can capture details of all SWIFT BICs are maintained through the 'Authorised SWIFT BICs for Customer Account' screen. Click the 'BIC' button in the 'Islamic Customer Accounts Detailed' screen to invoke this screen.

| BIC Code * | Description |
|------------|-------------|
| | |

You can enter the following details in this screen:

Account Number

The system defaults the account number of the customer in this field.

BIC Code


Specify the BIC here. You can choose any valid BIC maintained in the 'BIC Code Maintenance' screen.

Description

The system displays the description for the corresponding BIC that you have specified.

2.3.10 Specifying Deposits Details

Click the 'Deposit' button in the 'Islamic Customer Accounts Detailed' screen to invoke 'Deposits' screen, for additional information relating to the handling of the deposit, The 'Deposits' screen will be displayed.



The screenshot shows a window titled 'Deposits' with a blue header and footer. The main area contains four input fields: 'Auto Deposit Balance' (text box), 'Sweep Type' (dropdown menu showing 'No Sweep'), 'Master Account Number' (text box), and 'Rate' (text box). At the bottom right, there are two buttons: 'Ok' and 'Exit'.

You can enter the following details in this screen:

Auto Deposit Balance

This indicates the amount that got auto deposited into the account

Sweep Type

The drop-down list shows the following values:

- -1 - No sweep
- 0 - Default from A/c
- 1 - Sweep if instructed

Master Account No

Specify the master account number for the deposit account simulated.

Rate

Select the rate to be applied for the conversion. The options available are Buy rate, Mid Rate or the Sell Rate.

2.3.11 Specifying Instructions Details

You can maintain Account Operating Instructions for a branch and customer account combination. The operating instructions are different from the standing instructions and merely indicate the instructions to be borne in mind when operating a customer account.

The instructions are maintained through the 'Islamic Customer Accounts Detailed' screen invoked by clicking the 'Instructions' button.

You can enter the following details in this screen:

Date of Last Maintenance

The current system date is also displayed

Instructions

Specify the instructions to be borne in mind when operating a customer account

Conditions

At the time of maintaining an instruction, you can also specify a condition for displaying the instructions when transactions pertaining to this account are being processed. The instruction will be displayed to you when the condition is satisfied.


The sign-on branch code is defaulted when you maintain a new instruction. The current system date is also displayed. You can select the customer account for which you want to maintain an operating instruction, from the available option-list.

On selection of the account, the description gets displayed in the adjacent field.

At the time of maintaining an instruction, you can also specify a condition for displaying the instructions when transactions pertaining to this account are being processed. The instruction will be displayed to you when the condition is satisfied.

2.3.12 Specifying Standing Instructions Details

Instruction summary are maintained through the 'Instruction Diary Summary' screen. Click the 'Standing Instructions' button in the 'Islamic Customer Accounts Detailed' screen to invoke this screen.



Here you can view the following details:

- Authorization status
- Record status
- Instruction number
- Unit type
- Unit value
- Branch code
- Instruction
- Instruction type

2.3.13 Specifying Linked Entities Details

A customer of your bank can have relationships with any other customer of your bank. Also, a customer of your bank could be a joint account holder with another customer of your bank. You can capture these details when you set up the CIF or customer account.

For linking a customer account you need to specify details of the relationship for the account. Click the 'Linked Entities' button in the 'Islamic Customer Accounts Detailed' screen. The 'Linked Entities' screen will be displayed.

| Customer * | Customer Name | Relations * | Include Relationship |
|----------------------|----------------------|----------------------|--------------------------|
| <input type="text"/> | <input type="text"/> | <input type="text"/> | <input type="checkbox"/> |

You can enter the following details in this screen:

Customer

Select the customer from the option list with whom you want to establish the relationship with the customer account that you are maintaining.

Description

In this field, the system displays the name of customer that you have selected in the previous field. You cannot change the description.

Relationship

You have to choose a relationship code to establish a relationship between the customer being selected and the customer account you are maintaining.

By default, the system will select the customer of the account as the Primary Holder. This is a pre-shipped relationship and you will not be allowed to change the relationship.

2.3.14 Specifying REG Details

For a customer account, you can indicate whether check deposits to the account must be considered for Reg CC availability. You can indicate this in the Reg Details screen, which you can invoke by clicking the 'REG' button in the 'Islamic Customer Accounts Detailed' screen

A customer account using an account class for which Regulation D limits are applicable, inherits the applicability of Regulation D limits. However, you can make changes to the details, if necessary.

In the 'Islamic Customer Accounts Detailed' screen, click the 'REG' button to invoke the 'Reg Details' screen, where you can specify the Regulation D applicability details.



The screenshot shows a window titled "Reg Details" with a blue header bar. Inside the window, there are several controls: a checkbox labeled "Reg D Applicable", a dropdown menu labeled "Reg D Period", a section labeled "Periodicity" with three radio buttons: "Monthly", "Statement Cycle", and "None", and another checkbox labeled "Reg CC Availability". To the right of these controls are two text input fields labeled "Start Date" and "End Date". At the bottom right of the window, there are two buttons: "Ok" and "Exit".

You can enter the following details in this screen:

Reg D Applicable

Indicate whether the Regulation D limits are applicable for the account

Periodicity

If you indicate the periodicity of Regulation D applicability as 'Statement Cycle', the restricted transactions would be counted over the primary statement cycle defined for the customer account.

Reg CC Availability

Check this box if the check deposits into this account should be considered for Regulation CC aggregation.

Indicating Reg D Period Details

Start Date

The start date for Regulation D applicability is first set to be the date on which you mark the availability option in this screen. Subsequent to the first period, the EOD process would update the start date according to the periodicity defined.

End Date

Subsequent to the first period, the EOD process would update the end date according to the periodicity defined.

You can define whether the Regulation D limits are applicable for the account, and the period over which the limits would be applicable. If you indicate the periodicity of Regulation D applicability as 'Statement Cycle', the restricted transactions would be counted over the primary statement cycle defined for the customer account.

The start date for Regulation D applicability is first set to be the date on which you mark the availability flag in this screen. Subsequent to the first period, the EOD process would update the start and end dates according to the periodicity defined.

If you indicate the periodicity of Regulation D applicability as 'Statement Cycle', the restricted transactions would be counted over the primary statement cycle defined for the customer account.

2.3.15 Specifying Account Status Details

If you do not want the Islamic account class details to be propagated to the account as well, you have the option of maintaining the status codes and the reporting lines exclusively for an account. You can achieve this through the 'Status Details' screen. Click the 'Account Status' button in the 'Islamic Customer Accounts Detailed' screen to invoke it.

The screenshot shows a software window titled "Status Details". It contains several input sections: "Account" with "Branch *" and "Account *" fields; "Account Status" with "Status" and "Description" fields; "Reporting Lines"; "GL Lines" with "Credit" and "Debit" fields; "Central Bank Lines" with "Credit" and "Debit" fields; and "Head Office Lines" with "Credit" and "Debit" fields. At the bottom right, there are "Ok" and "Exit" buttons. A navigation bar in the "Account Status" section shows "< 1 Of 1 >".

The details maintained for the Islamic account class will be displayed in this screen. However, you are allowed to make amendments to the defaulted values.

Here you can capture the following details:

Branch Code

The system defaults the code of the current branch.

Account

The system defaults the account number from the main screen.

Status

You can select the different status codes applicable to the account class, in this field. Use the Add icon to define each status and the attributes for the same. You can use the navigation icons to move from one status to the other.

On selection of the status, the associated description will be displayed alongside.

Specifying Reporting Line

Debit and Credit GL Line

Select the debit GL account, to which all debit balances within a specific account class will report to, when it moves to the status being defined. You can identify the debit GL from the list of existing GLs. Likewise, all credits within a particular account class will report to the GL account that you have identified to track credits.

Central Bank Line

Debit

Specify the Central Bank line to which this account will report to, if it is in debit. This line is maintained in the 'Reporting Lines Maintenance' screen.

Credit

Specify the Central Bank line to which this account will report to, if it is in credit. This central bank line is maintained in the 'Reporting Lines Maintenance' screen.

Head Office Line

Debit

Specify the Debit Head Office GL to which the account will report, if they are in a debit.

Credit

Specify the Credit Head Office GL to which this account will report, if it is running in credit.

2.3.16 Specifying Restrictions Details

You can place restrictions on transactions involving customer accounts both at a transaction code level as well as at a product level. In other words, you can decide whether you would like to use the accounts for processing:

- Debit transactions
- Credit transactions
- Both

The restrictions maintained for the account class will default to all the accounts that are linked to the account class. At the individual account level, however, you can apply special conditions by changing the restrictions.

To maintain the restrictions, click the 'Restriction' button in the 'Islamic Customer Accounts Detailed' screen. The 'Products and Transaction Codes Restriction' screen will be displayed.

Product Details

Product List Allowed
 Disallowed

Special Condition Applicable
 Not Applicable

| Product | Description | Debit | Credit |
|---------|-------------|--------------------------|--------------------------|
| | | <input type="checkbox"/> | <input type="checkbox"/> |

Transaction Details

Transaction List Allowed
 Disallowed

Special Condition Applicable
 Not Applicable

| Transaction Code | Description | Debit | Credit |
|------------------|-------------|--------------------------|--------------------------|
| | | <input type="checkbox"/> | <input type="checkbox"/> |

Ok Exit

Specifying Product Restriction

Special Condition

By default, the restrictions maintained at the account class level will be displayed here. When you define transaction code or product restriction attributes for an account itself, rather than for the account class to which it belongs, it is referred to as a Special Condition. You can apply special conditions by selecting the option 'Special Condition Applicable' at the account level. If you opt to define special conditions for an account the 'restrictions' defined for the Account Class, to which the account belongs, will NOT apply to this account. If you wish to continue with the account class restrictions, opt for 'Special Condition Not Applicable'.

Restriction Type

Specify the restriction type here. The options available are:

- Allowed – If you select this, the products entered in the multi entry block will be allowed for that customer account
- Disallowed – If you select this option, the products entered in the multi entry block will be disallowed

Product Code

You can select the products and specify the type of transaction (Dr, Cr or both) that you would like to allow/disallow for each product. In contracts involving the selected products, the accounts would be used for processing the selected type of transaction. For instance, assume that for the account A1, you have allowed 'Dr' for the product ABCD. This would mean that if a Dr entry for the product ABCD is passed to the account, A1, it would go through but in case a Cr entry is passed for this product, then the system will display a message indicating that the transaction is restricted for the account.

Description

The system displays the description for the product code that which you have specified.

Dr

During transaction processing, the system will validate whether any restrictions are placed on the account based on either product and/or transaction code. If you have indicated to allow Dr Transactions for the product ABCD, and attempt to post a credit entry, the system will seek an override. You can continue the transaction, despite the restrictions, by providing appropriate reasons for the same.

During maintenance or online operations, in the respective contract screens for the restricted transactions, when you specify the customer account, the system checks whether the account is restricted for the product that has been selected, or the debit/credit transaction type. If so, an override is sought when such contracts are saved.

Cr

During transaction processing, the system will validate whether any restrictions are placed on the account based on either product and/or transaction code. If you have indicated to allow Dr transactions for the product ABCD, and attempt to post a credit entry, the system will seek an override. You can continue the transaction, despite the restrictions, by providing appropriate reasons for the same.

During maintenance or online operations, in the respective contract screens for the restricted transactions, when you specify the customer account, the system checks whether the account is restricted for the product that has been selected, or the debit/credit transaction type. If so, an override is sought when such contracts are saved.

Specifying Transaction Restriction

Special Condition

By default, the restrictions maintained at the account class level will be displayed here. When you define transaction code or product restriction attributes for an account itself, rather than for the account class to which it belongs, it is referred to as a Special Condition. You can apply special conditions by selecting the option 'Special Condition Applicable' at the account level. If you opt to define special conditions for an account the 'restrictions' defined for the Account Class, to which the account belongs, will NOT apply to this account. If you wish to continue with the account class restrictions, opt for 'Special Condition Not Applicable'.

Restriction Type

Specify the restriction type here. The options available are:

- Allowed – If you select this, the products entered in the multi entry block will be allowed for that customer account
- Disallowed – If you select this option, the products entered in the multi entry block will be disallowed

Transaction Code

Likewise, you can maintain restrictions for transaction codes as well.

Description

The system displays the description for the transaction code that you have specified.

Dr

During transaction processing, the system will validate whether any restrictions are placed on the account based on either product and/or transaction code. If you have indicated to allow debit transactions for the product ABCD, and attempt to post a credit entry, the system will seek an override. You can continue the transaction, despite the restrictions, by providing appropriate reasons for the same.

During maintenance or online operations, in the respective contract screens for the restricted transactions, when you specify the customer account, the system checks whether the account is restricted for the product that has been selected, or the debit/credit transaction type. If so, an override is sought when such contracts are saved.

Cr

During transaction processing, the system will validate whether any restrictions are placed on the account based on either product and/or transaction code. If you have indicated to allow debit transactions for the product ABCD, and attempt to post a credit entry, the system will seek an override. You can continue the transaction, despite the restrictions, by providing appropriate reasons for the same.

During maintenance or online operations, in the respective contract screens for the restricted transactions, when you specify the customer account, the system checks whether the account is restricted for the product that has been selected, or the debit/credit transaction type. If so, an override is sought when such contracts are saved.

2.3.17 Specifying Currency Limits Details

Currency limits are maintained through the 'Currency Limits Details' screen. Click the 'Currency Limits' button in the 'Islamic Customer Accounts Detailed' screen to invoke this screen.

The screenshot shows a software window titled "Currency Limits Details". At the top, there are two input fields labeled "Branch *" and "Account *". Below these is a section titled "Currency Limits Details" containing a table with three columns: "Currency *", "Credit Limit Amount", and "Debit Limit Amount". The table has one row with empty input fields. At the bottom right of the window are "Ok" and "Exit" buttons.

In this screen, you can enter the following details:

Account Number

The system displays the customer account for which PC limits are being maintained.

Currency

Specify the currency in which the auto exchange limits should be maintained. The adjoining option list displays the currency codes maintained in the system. You can choose the appropriate one.

Cr Lmt Amt

Specify the credit limit amount in the chosen currency.

Dr Lmt Amt

Specify the debit limit amount in the chosen currency.

2.3.18 Specifying MIS Details

To invoke the 'Management Information System' screen for an account, click the 'MIS' button in the 'Islamic Customer Accounts Detailed' screen, while opening/modifying the account. The entities defined for the customer will be picked up by default and these entities can be changed.

The screenshot shows the 'Management Information System' window. It contains several input fields and tables. At the top, there are fields for 'Branch', 'Account', 'MIS Group' (with a 'Default MIS Group' button), 'Rate Code', 'Link to Group', 'Calc Method', 'Rate Type' (set to 'Fixed'), 'Spread', 'Pool Code' (with radio buttons for 'Pool Code' and 'Account Level'), and 'Reference Rate'. Below these are three tables: 'Transaction MIS Codes' with columns for 'Address 2' and 'Cost Code'; 'Composite MIS Codes' with a column for 'Address 3'. At the bottom, there are 'Change Log' and 'Transfer Log' links, and 'Ok' and 'Exit' buttons.

For an account, the transaction type of MIS class will be picked up from the account class, along with the cost codes and pool codes. The composite type of MIS class will be defaulted from those defined for the customer. These too can be changed.

Branch

The current logged-in branch code is displayed here

MIS Group

For an account, the transaction type of MIS class will be picked up from the account class

Rate Code

Specify the rate code. Select the appropriate one from the adjoining option list, which displays all valid rate codes maintained in the system

Link to Group

If an MIS Group is linked, you can indicate whether the linkage with the group should always be maintained. If yes, any change to the MIS Group will automatically apply to the customer to whom the MIS Group is linked. If not, the entities defaulted for the customer will continue, even if they are changed subsequently for the group.

Rate type

If you have indicated that rates maintained for the individual account should be picked up for MIS refinancing you have to specify the Rate Type that is to be used. The options available are:

- Fixed
- Floating – Automatic – indicating that the system should pick up the refinancing rate associated with the account. Since the account number is linked to a Rate Code the system picks up the rate code associated with the account when the EOD processes are run to refresh the various rates.

Select the appropriate.

Pool Code/Account Level

The Pool Code/Account Level to which the account class or product belongs should be defined.

Pool Code

For an account, the pool code will be picked up from the account class.

Transaction MIS Group

For an account, the transaction type of MIS class will be picked up from the account class.

Composite MIS Group

The composite type of MIS class will be defaulted from those defined for the customer.

Cost Code

For an account, the cost codes will be picked up from the account class.

2.3.19 Specifying Change Log Details

To invoke the 'Change Log' screen for an account, click the 'Change Log' button in the 'Islamic Management Information System' screen.

The screenshot shows a window titled "Change Log" with a blue header bar. Below the header, there are two input fields: "Branch" and "Account". Underneath, the "Change Log Details" section features a table with the following columns: "MIS Class *", "Transaction Date *", "Old MIS Code", and "New MIS Code". The table currently contains one row with empty cells. Above the table, there are navigation controls including "1 Of 1" and a "Go" button. At the bottom right of the window, there are "Ok" and "Exit" buttons.

Branch Code


The current logged-in branch code is displayed here.

Account

The current logged-in account number is displayed here.

Specifying Transfer Log Details

To invoke the 'Log' screen for an account, click the 'Change Log' button in the 'Islamic Management Information System' screen.



| Branch | Period | Financial Year | GL Code | Transfer Indicator | MIS Class | Transaction Date | Old MIS | New |
|--------|--------|----------------|---------|--------------------|-----------|------------------|---------|-----|
|--------|--------|----------------|---------|--------------------|-----------|------------------|---------|-----|


Here you can capture the following details:

Account Number

This is the account number of the deposit. If you specify an account that is disallowed for your user id and move to the next field the system will throw up an error/override. The restricted accounts for users ids are maintained in the 'User Account Class Restrictions' screen. The system will perform this validation for default settlement pick up also.

2.3.20 Specifying Cheque Book Request Details

Click on the 'Cheque Book Request' button in the 'Islamic Customer Accounts Maintenance' screen to invoke the Cheque Book Request screen.



You will be able to invoke this screen, only if you have checked the 'Auto Cheque Book Request' check box in the 'Islamic Customer Accounts Maintenance' screen.

Branch

The branch detail gets defaulted from the account branch.

Account

The system displays the account number.

First Check Number

Specify the number of the first cheque leaf of the cheque book.

Check Leaves

Specify the number of cheque leaves in the cheque book.

Cheque Book Type

Specify the cheque book type. The adjoining option list displays the cheque types maintained in the system. You can choose the appropriate one.

Order Date

The order date gets defaulted as the current date. However you can change the same.

Order Details

Specify the order details.

Language Code

Specify the code of the language. The adjoining option list displays all valid language codes maintained in the system. You can choose the appropriate one.


Request Status

The value of this will be defaulted to 'Requested' status.

Click on 'Ok' to save the cheque book request details.

2.3.21 Specifying Card Request Details

Click on the 'Card Request' button in the 'Islamic Customer Accounts Maintenance' screen to invoke the Debit Card Request Details screen.



The screenshot shows a window titled "Debit Card Details" with a blue header and footer. The main area is white and contains the following fields and controls:

- Branch Code * (text input)
- Request Reference Number * (text input)
- Customer No * (text input)
- Account No * (text input)
- Card products (text input with a "Default" button)
- Card BIN (text input)
- Name On Card (text input)
- Card Number (text input)
- Card Application Date (text input)
- Primary Card (checkbox, checked)
- Card Status (dropdown menu, currently showing "Requested")

At the bottom right of the window, there are "Ok" and "Exit" buttons.

You will be able to invoke this screen, only if you have checked the 'Auto Debit Card Request' check box in the 'Islamic Customer Accounts Maintenance' screen.

Branch Code

The branch detail gets defaulted from the account branch.

Request Reference Number

The reference number of the request is auto generated and populated, when you click on the 'Default' button.

Customer No

The customer number of the account gets defaulted.

Account No

The account number gets defaulted from account details.

Card Products

Specify the card products. The adjoining option list displays the card products maintained in the system. You can select the appropriate ones.

Card Bin

Specify the card bin. The adjoining list displays the card bins maintained for the specified card product. You can choose the appropriate one.

Name on Card

Specify the customer name that is to be printed on card.

Card Number

Specify the debit card number to be requested. The adjoining option list displays the valid debit card numbers maintained in the system. You can choose the appropriate one.

Card Application Date

The card application date would be defaulted as the current date of the branch. However you can change the same.

Primary Card

The primary card check box remains checked by default.

Card Status

The status of the card will be defaulted to 'Requested'

Click on 'Ok' to save the Debit card request details.

2.3.22 Specifying Linked Deposit Details

You can maintain the linked deposit details in the Mudarabah Sweep details screen. Click on the Deposit Linkage button in the Islamic customer Account Details screen to invoke this screen.

| Linkage Order | Deposit Branch | Deposit Account * | Maturity Date | Original Deposit Amount | Linkage Percent | Linked Amo |
|---------------|----------------|-------------------|---------------|-------------------------|-----------------|------------|
| 1 | | | | | 0 | |

Branch Code

The system defaults the customer account branch code from the Islamic customer accounts detailed screen.

Account Number

The system defaults the account number from the Islamic customer accounts detailed screen.

Linkage Details

Order of Linkage

Specify the order in which the deposit account is considered for sweep.

TD Account

Select the linked TD account from the adjoining option list.

Deposit Account

Select the deposit account from the adjoining option list.

TD Maturity Date

The system displays the maturity date of the linked deposit.

Original Deposit Amount

The system defaults the deposit amount at the time of linkage.

Linkage Percentage

Specify the percentage of amount to be linked. Linked percentage can be modified if the utilization amount is zero.

Linked Amount

The system displays the total of the linked amount.

Available Amount

The system displays the current available amount in the deposit for sweep.

Utilized Amount

The amount utilized for sweep is displayed here.

When the Account Currency Available Balance becomes negative then the linked deposit is in the same order as linked in account screen.

Note

If Mudarabah deposit closure happens on the day of maturity then:

- The deposit account will be liquidated with the existing balance in the deposit even if there is some utilized amount in the deposit. This happens during ICEOD batch processing of the BOD stage.
- Linkage to the CASA account will not exist.

If Mudarabah deposit rollover happens on the day of maturity day then:

- There will be a rollover of the TD account as part of ICEOD.
 - Linkage details will remain the same.
-

If linked deposit details are given for an account without checking Mudarabah Sweep in the Islamic Customer Account screen, then the system displays the error message as, "Linked deposit details can be given only if the flag 'Mudrabah sweep' is checked."

If the deposit is already linked to some other CASA, then the available amount for utilization is less than the TD booking amount. In this case if the linked amount is not available in the deposit account, then the system displays an error message: as, "Creation of amount block failed since the available amount, <available amount in deposit > , is less than the linked amount, <linked amount > , in the deposit, <deposit account "

2.3.23 Specifying Statement Details

Preferences regarding the type of account statement - detailed or summary or none at all, as well as the statement frequency, including whether multiple statements are to be generated, are specified for the account class in the Islamic Account Class screen. These details are applicable to all accounts linked to the account class. While maintaining customer account details in the 'Islamic Customer Accounts Detailed' screen, these details are defaulted.

For a particular customer account, you may redefine the default specification. The details specified at the account level will supersede those specified for the account class. To specify

account level details, click the 'Statement' button. The statement details table will be displayed.

Account Number

The system displays the account number for which you are setting the statement details

Primary A/c Statement

This refers to the type of statement to be generated periodically by the system, for this account. You can specify whether you want a detailed or summary statement or if you do not want a statement for this account at all.

Cycle

You can specify the frequency for generating the account statements. To specify the frequency of the statements, click on the adjoining drop-down list. The following list is displayed:

- Annual
- Semi-annual
- Quarterly
- Monthly
- Fortnightly
- Weekly
- Daily

On

For a weekly statement you specify the day of the week on which account statements should be generated and for fortnightly and monthly statements the dates of the month. To specify for weekly statements, click on the adjoining drop-down list. The following list of days will be displayed:

- Monday
- Tuesday
- Wednesday
- Thursday
- Friday
- Saturday
- Sunday

To specify for monthly statements enter a number between 1 and 31 (corresponding to the system date)

If you set the statement date to 30, then account statements will be generated on:

- The last working day for months with < 30 days
- For months with 30 days on the 30th; if 30th is a holiday on the next working day

If you set the statement date to 31, then account statements will be generated on:

- The 31st for month with 31 days; if 31st is a holiday on the next working day
- The last working day for months < 31 days

For a fortnightly statement you could specify 1 and 15

For all other cycles, account statement will be generated on the last day of that cycle

Generate Stat. Only On Movement

You can indicate that an account statement should be generated for the customer's account only when there has been a movement of funds into the account or when funds have been transferred out of the account.

For instance, let us assume that on the August 21, 2001, you have set the account statement generation frequency as Daily for the account LI020804. On the September 5, 2001, there has been no movement of funds in the particular account. If you have opted for the Generate Only on Movement option, the system will not generate a statement message for September 5, 2001.

If you choose not to enable this option, account statements will be generated regardless of whether there has been a movement of funds or not.

Display IBAN in Advices

If you would like to print the IBAN number of the customer on advices sent to the customer, you can enable the Display IBAN in Advices option by checking it. This specification will be defaulted from the account class linked to the customer account. You will be allowed to change it for a specific account.

You can choose to print the IBAN Number in advices that are sent to the customer by enabling the check box positioned next to the Display IBAN on Advices field. If the Display IBAN on Advices check box is disabled, you can enable this option by checking the box. Consequently, the IBAN Account Number will be printed on all customer correspondence (Debit/Credit advices) involving the particular account.

Because of choosing to print IBAN numbers in the correspondence sent to the customer, the Oracle FLEXCUBE account number will be replaced by the IBAN number. The lists of SWIFT messages that will include IBAN account numbers are as follows:

- MT940 – Customer Statement Message
- MT950 – Statement Message
- MT900 – Confirmation of debit
- MT910 – Confirmation of Credit

Note

While processing incoming payments, the system checks to see whether the account involved is an IBAN account. If the account is an IBAN account, it will be processed with the corresponding Oracle FLEXCUBE account number.

Secondary A/c Statement

This refers to the type of statement to be generated periodically by the system, for this account. You can specify whether you want a detailed or summary statement or if you do not want a statement for this account at all.

Cycle

You can specify the frequency for generating the account statements. To specify the frequency of the statements, click on the adjoining drop-down list. The following list is displayed:

- Annual
- Semi-annual
- Quarterly
- Monthly
- Fortnightly
- Weekly
- Daily

On

For a weekly statement you specify the day of the week on which account statements should be generated and for fortnightly and monthly statements the dates of the month. To specify for weekly statements, click on the adjoining drop-down list. The following list of days will be displayed:

- Monday
- Tuesday
- Wednesday
- Thursday
- Friday
- Saturday
- Sunday

To specify for monthly statements enter a number between 1 and 31 (corresponding to the system date).

If you set the statement date to 30, then account statements will be generated on:

- The last working day for months with < 30 days
- For months with 30 days on the 30th; if 30th is a holiday on the next working day

If you set the statement date to 31, then account statements will be generated on:

- The 31st for month with 31 days; if 31st is a holiday on the next working day
- The last working day for months < 31 days

For a fortnightly statement, you could specify 1 and 15

For all other cycles, account statement will be generated on the last day of that cycle

Generate Stat. Only On Movement

You can indicate that an account statement should be generated for the customer's account only when there has been a movement of funds into the account or when funds have been transferred out of the account.

For instance, let us assume that on the August 21, 2001, you have set the account statement generation frequency as Daily for the account LI020804. On September 5, 2001, there has been no movement of funds in the particular account. If you have opted for the Generate Only on Movement option, the system will not generate a statement message for September 5, 2001.

If you choose not to enable this option, account statements will be generated regardless of whether there has been a movement of funds or not.

Tertiary A/c Statement

This refers to the type of statement to be generated periodically by the system, for this account. You can specify whether you want a detailed or summary statement or if you do not want a statement for this account at all.

Cycle

You can specify the frequency for generating the account statements. To specify the frequency of the statements, click on the adjoining drop-down list. The following list is displayed:

- Annual
- Semi-annual
- Quarterly
- Monthly
- Fortnightly
- Weekly
- Daily

On

For a weekly statement you specify the day of the week on which account statements should be generated and for fortnightly and monthly statements the dates of the month. To specify for weekly statements, click on the adjoining drop-down list. The following list of days will be displayed:

- Monday
- Tuesday
- Wednesday
- Thursday
- Friday
- Saturday
- Sunday

To specify for monthly statements enter a number between 1 and 31 (corresponding to the system date).

If you set the statement date to 30, then account statements will be generated on:

- The last working day for months with < 30 days
- For months with 30 days on the 30th; if 30th is a holiday on the next working day

If you set the statement date to 31, then account statements will be generated on:

- The 31st for month with 31 days; if 31st is a holiday on the next working day
- The last working day for months < 31 days

For a fortnightly statement, you could specify 1 and 15

For all other cycles, account statement will be generated on the last day of that cycle

Generate Stat. Only On Movement

You can indicate that an account statement should be generated for the customer's account only when there has been a movement of funds into the account or when funds have been transferred out of the account.

For instance, let us assume that on the August 21, 2001, you have set the account statement generation frequency as Daily for the account LI020804. On September 5, 2001, there has been no movement of funds in the particular account. If you have opted for the Generate Only on Movement option the system will not generate a statement message for September 5, 2001.

If you choose not to enable this option, account statements will be generated regardless of whether there has been a movement of funds or not.

Exclude Same Day Reversal trns from Stmt

If you do not wish transactions booked and reversed on the same day to be reflected in the account statement, you can specify the preference here. This feature is applicable only for the customer account legs and not for the related GL legs. Also, reversals made through the DE module will not be considered for exclusion.

This specification is defaulted from the account class linked to the account. You can change it for a specific account.

Statement Account

A customer may have two or more accounts with your bank but may desire to receive a single consolidated account statement.

Oracle FLEXCUBE allows you to link accounts. For the particular account whose statement preferences you are defining you can indicate the parent account to which the account should be linked for statement generation purposes.

The statement account is applicable for all type of account statements (Primary, Secondary and Tertiary). If the statement account has been specified, you cannot enter other statement details.

If the statement account is not specified for a particular account then the account can be a statement account for other accounts. If statement accounts have been maintained, during EOD, the account statement will not be individually generated for the child accounts. Instead a consolidated account statement would be generated based on the frequency specified for the parent account.

While closing a parent account, a message will be shown requesting removal of the parent-child account linkage.

Note

Even while generating ad-hoc statements you can indicate whether linked account details should be displayed in the generated report.

2.3.24 Specifying Limits Details

A bank lends overdraft credit facility to both its corporate and individual customers. For a corporate customer a bank defines a credit line based limit. For an individual customer the bank gives an account based overdraft limit. In the Oracle FLEXCUBE system, an account-based limit can co-exist with the credit-based limit.

For a credit line based limit, one customer is designated as a liability customer who is assigned a credit limit. Other customers are designated as subsidiaries of his liability limit. Thus these subsidiary customers are linked to a main credit line of the liability customer. There can be several such liability customers to whom a few subsidiary customers are linked.

A credit line has three basic levels of limits.

- Overall limit -- this is the maximum credit exposure that a bank is willing to take for a liability group.
- Main Line Limit -- this is typically an overall limit for a product. It can be used to sub-divide the overall limit by other criteria, such as, customer, industry, region and so on.
- Sub Line limit -- this is used to allocate the main line credit limit to specifics. For example, finances into short term long term finances.

Also, the same customer may have different overdraft limit for different accounts. This credit is always granted for a specified time period and therefore referred to as temporary.

To specify the credit line details, click the 'Limits' button and invoke the 'Account – Limits' screen will be displayed. The Limit currency specified in the 'Islamic Customer Accounts Maintenance' screen is displayed. Limit currency refers to the currency in which the bank wants to give credit facility to this account.

Note

This button appears enabled only if the function Id LMTACRES has been added to your User Role'. You will then be able to View/Modify/Add (Define) the details of limits main-

tained at the Account Level. If this function ID has not been added to your User Role, this button will appear disabled.

In this table, you can define the following attributes for a credit line.

- Temporary Overdraft Limit
- Sub-limit
- The date from which this credit line is effective
- The expiry date of this credit line
- The credit line to which you want to link this customer
- Uncollected Funds Limits
- Credit Transaction Limits

Temp. OD Start

The start and end dates represent the dates from which the temporary overdraft limit becomes effective upto the date on which it should cease to be effective.

Temp. OD Start

The start and end dates represent the dates from which the temporary overdraft limit becomes effective upto the date on which it should cease to be effective.

Credit Line

You can indicate the credit line to which you would like to link the customer to. A list of all the credit line codes maintained in the system will be displayed in the option list. You can select the appropriate.

Netting Required

To process linked accounts, which are marked for referral, you will need to enable the Netting Required option. This option is defaulted from the Credit Line associated with the customer account. If you change the default option, the system displays an override message.

Temp. OD Limit

The temporary OD limit is the limit upto, which any overdraft is allowed, for a specified time period, over and above the limit set for this account.

This limit is independent of any credit line linked to this account. This is mostly used for short term overdrawing.

Sublimit

The sub-limit represents that portion of the total credit amount that can be used by this customer account. The sub-limit need be input only when the account is to be limited to a portion of the available line amount.

While passing transactions to an account with a sub-limit the first credit check made is against this sub-limit amount. If the sub-limit is crossed, you will be asked for an override.

Uncoll. Funds Limit

The uncollected funds limit represents the credit transaction amounts that have not been collected as of the current day. You can set the limit upto which withdrawal is allowed against uncollected funds.

The uncollected opening balance is reset with the current uncollected balance amount during the EOD process. This amount is to be considered when calculating Central Limit availability.

Offline Limit

This is the limiting amount till which transactions will be carried out between account(s) for the account class you are defining here, between branches when the database connectivity is not functional.

Daylight Limit

The daylight limit is the limit up to which an overdraft is allowed for the business day. The daylight limit will be added to temporary overdraft to calculate the available balance if EOD is not in progress. Daylight limit is not considered during EOD.

Note

You can specify the daylight limit only if 'Daylight Limit' option is checked in linked 'Account Class - Preferences' screen. By default, the system will display the value as zero. You can however change it.

SOD Notification %

Specify the consolidated percentage utilization used for notification of the limit breach under the SOD.

For more information on SOD Alert Generation, refer topic 'Generating Alert for SOD Utilization' later in this chapter.

Cr Transaction Limit

The limit for credit transactions in the account currency. When a transaction exceeds this limit, an override is displayed. The override requires a dual authorization to save the transaction.

Credit Start Date

This is the date from which this monitoring comes into effect. The check will be performed for all entries to customer accounts with transaction (booking) date greater than or equal to the start date.

Credit Rev Date

This is the date on which you would wish to revise this limit. The limit check will continue irrespective of the date maintained here. The revision date must be greater than the start date and can be left blank.

Specifying TOD Renewal Details

Renew TOD

Check this box if you want to renew TOD.

Renew Frequency

Specify the renew frequency from the drop-down list. The available options are:

- Days
- Month

Renew Units

Specify the renew units.

The following validations need to be done for the frequency:

- If 'Renew Frequency' chosen is 'Days' then 'Renew Units' cannot be greater than 366
- If 'Renew Frequency' chosen is 'Month' then 'Renew Units' cannot be greater than 12

Next Renewal Limit

Specify the TOD amount that can be renewed in next cycle.

2.3.25 Specifying Joint Holders Details

For a joint account type of customer account you need to specify details of the other joint holders of the account. Click the 'Joint Holders' button to display the joint account holder's screen.

| Customer Number | Customer Name | Joint Holder Type | Start Date | End Date |
|--------------------------|---------------|----------------------|------------|----------|
| <input type="checkbox"/> | | Authorized Signatory | | |

Indicate the following details:

Account Number

The system displays the account number here

Customer Number

The system defaults the customer number based on the selected account number.

Branch Code

The system displays the branch code of the current branch

List of Joint Holders

You can add the joint holder details in this section if the selected account type is 'Joint'. Maintain the following details:

Customer Number

Specify the customer Id for the joint holder. The adjoining option list displays the list of all valid customer numbers. Select the appropriate one.

Customer Name

The system displays the customer name based on the selected customer number.

Joint Holder Type

Specify the type of authority. Select the appropriate one from the drop-down menu. The options are:

- Authorized Signatory
- Customer Contact Person
- Guardian
- Custodian
- Developer
- Guarantor
- Joint and First
- Joint and Other
- Joint or First
- Joint or Other
- Nominee
- Related for Enquiry
- Solicitor
- Sole Owner
- Third Party
- Trustee
- Valuer
- Power of Attorney

Start Date

Specify the date from which the joint holding of the account begins.

End Date

Specify the date on which the joint holding of the account ends.

Note

Note the following:

- After the Joint holder expires the corresponding signature details of the joint holder will be deleted in the account signatory details and the same will be reflected in the Account Signatory History screen
- If the end date expires, the system does not allow you to save the customer account in case of amendment in the joint holder details.
- If you modify a joint holder record from 'STDJHMNT' screen and s not authorized yet, the system will not allow you to modify the joint holder details from 'STDCUSAC'

screen and vice-versa, until it is authorized. However, you can modify the account details other than joint holder details.

- You can enter the joint holder details only if 'Account Type' is 'Joint'. If the account type is 'Joint' then it is mandatory to specify the details of at least one joint holder.

2.3.26 Specifying UDF Details

User defined fields are maintained through the 'User Defined Fields' screen. Click the 'Fields' button in the 'Islamic Customer Accounts Detailed' screen to invoke this screen.

| Field Name * | Value | Value Description |
|--------------|-------|-------------------|
| | | |

2.3.27 Specifying Deposits Instruction Details

Deposits instructions are maintained through the 'Deposits Instructions' screen. Click the 'Deposits Instructions' button in the 'Islamic Customer Accounts Detailed' screen to invoke this screen.

Branch
Account *
Deposit Account Class
Customer
Account Currency
Sweep Branch
Deposit Currency
Sweep To Account
Sweep Amount
Sequence Number
Years
Months
Days
Sweep Multiple Of
Minimum Required Balance
Source Code
External Reference Number

Here you can capture the following details:

- Branch Code - The branch code of the branch which is to be associated with the account

- Account - Specify the account number of the customer. Select the account number from the adjoining option list
- Account Class - This is the account class to which the account is linked
- Customer - The customer for whom you are maintaining the deposit instructions
- Currency - Currency of the particular account
- Sweep Branch - Indicate the branch to which the sweep is carried out
- Deposit Currency - The currency in which the deposit is made
- Sweep To Account - Indicate the account to which the sweep is carried out
- Sweep Amount - This is the deposit amount
- Seq No - The system generated sequence number for the instruction you are maintaining
- Deposit Tenor - Tenor for the deposits that are opened under an account class, in terms of years, months and days
- Sweep Multiple Of - The sweep can only be in multiples of the sweep specified
- Minimum Required Balance - The minimum balance indicates that only the amounts above this limit will be used for auto creating deposits
- Source Code - The code assigned for the sweep
- External Reference Number – The external reference number
- Retry Till Date - The instructions specified will be invalid after this date Any failed sweeps after this date will not be picked up for processing the next day
- Start Date – The start date of the application of the deposit instruction maintained.

The auto deposit is triggered during EOD when the account balance exceeds the minimum required balance.

Auto Deposit is created if the following conditions are satisfied:

- 'Auto Deposit' is checked and deposit instructions are given for the account.
- Amount utilized from the linked deposit accounts are swepted out.
- Account currency balance is greater than 'Minimum Required Balance'.

2.3.28 Specifying Billing Parameters Details

Billing parameters are maintained through the 'Billing Parameters' screen. Click the 'Billing Parameters' button in the 'Islamic Customer Accounts Detailed' screen to invoke this screen.

The screenshot shows the 'Billing Parameters' window. It has a title bar with a diamond icon and the text 'Billing Parameters'. The main area contains the following fields:

- Branch: [Text Box]
- Account: [Text Box]
- Consolidating Branch: [Text Box]
- Consolidating Account: [Text Box]
- Consolidating Currency: [Text Box]
- Billing Liquidation: [Dropdown Menu] (set to 'Auto')
- Settlement Branch: [Text Box]
- Settlement Account: [Text Box]
- Settlement Currency: [Text Box]
- Direct Debit
- Payable Bank: [Text Box]
- Account: [Text Box]
- Name: [Text Box]
- Agreement Id: [Text Box]

Below these fields is a section titled 'Billing Details'. It contains a table with one row: 'Billing Product *'. Above the table is a search bar with 'Go' and navigation icons. At the bottom right of the window are 'Ok' and 'Exit' buttons.

You will have to maintain a set of parameters for the billing module. While settling or liquidating the bill, the default parameters that you have maintained for the account involved in this module will be used.

The screen also displays the Product Code and Description of all Billing Products applicable to the account.

Consolidating Account

You can specify a consolidating account for the given account. From the option list you can choose:

- A different account number if you want to consolidate the charge under this account to a different account. The Consolidation account selected for this account should be in the same currency as this account. It also has to belong to the same branch as the specified account.
- The same account to indicate that there is no consolidation and an individual billing invoice is to be raised on this account

Billing Liquidation

You have two modes of liquidation i.e. Auto or Manual. The preference you have maintained for the billing product will be defaulted here. You can choose to change the mode for the specified account under the following scenarios:

- If Auto is chosen, then you have to specify whether the settlement is through a settlement account or through Direct Debit Instruction
- In case you want to raise Direct Debit instruction for the billing invoice amount, irrespective of whether the liquidation mode is Auto or Manual, you have to maintain the

details for Direct Debit details viz. Direct Debit Bank Code, Account, Name and Agreement ID fields.

- If you choose Manual option, then manual liquidation is possible only under the following four modes:
 - By Cash – through retail teller product
 - By Clearing – through outward clearing product
 - By Transfer – debit account in CASA module
 - By Direct Debit – through PC module

Note

If the consolidation account is different from the present account, then the system uses the liquidation parameters specified at the consolidation account level and liquidation parameters specified, if any, at this account level is ignored.

Settlement Account

As mentioned above, you need to specify the settlement account to enable automatic liquidation of billing.

For liquidating the billing amount and also for collecting the bill amount, the system makes use of the account specified here.

Maintaining direct debit details

If you have maintained the mode of settlement for auto liquidation of bills as Direct Debit instructions, you need to specify the following details:

- Payable Bank – Choose the bank from the option list. This indicates the bank code of the settlement account
- Account Number – Specify the account number for the settlement account
- Name – Specify the name of the debtor
- Agreement ID – Specify the agreement id on which the DD is to be generated

During liquidation, the direct debit contract is uploaded into the system in case you have maintained the settlement mode as direct debit transaction. The upload happens for both automatic liquidation and manual liquidation.

2.3.29 Specifying Account Signatory Details

Account Signatory details are maintained through the 'Signatory Details' screen. Click the 'Account Signatory' button in the 'Islamic Customer Accounts Detailed' screen to invoke this screen.

| Customer ID * | Relation Type | Signature Id * | Signatory Name | Signatory Type |
|---------------|---------------|----------------|----------------|----------------|
| | | | | |

Here you can capture the following details:

Branch

The system defaults the current branch here.

Account Number

This is the account number to which signatories are to being linked.

Account Description

The system displays the description for the account you have selected.

Customer Number

Enter the customer signatory you want to link to the account

You can link a customer signatory to an account either by:

- Click on the option list next to the Signatory Number. A list of customer signatory numbers, whose details have been captured will be displayed, along with their names. Pick up the signatory whom you want to make an account signatory for the account
- Keying-in the customer Signatory Number and Name directly, if the signatory number has not been maintained through the Customer Signatory details screen

Note

If the signatory ID that you specify has not been maintained, the System displays an override. On confirming the override, you will be allowed to save the signatory details. An error message is displayed if you enter a duplicate Signatory ID. Each time you capture a new Signatory ID at the account level you must identify the relationship of the signatory with the customer.

Customer Name

The system displays the name of the corresponding customer.

Minimum Number of Signatories

Specify the minimum number of signatories necessary to endorse an instrument involving the account.

Account Message

You can capture information about particular signatories. These messages could pertain to the name, number and the type of signatory your customer is. For instance you can capture a message like - "This signatory is a joint account holder with rights to sign instruments only up to US 8000".

Signatory Number

The system displays values maintained in CIF signatory for the customer number.

Signatory Name

The system displays the corresponding name of the signatory number specified.

Approval Limit

Specify the amount up to which the account signatory can approve for debits.

2.3.30 Specifying Interim Transactions Report Details

Interim Transaction reports are maintained through the 'Interim Transaction Reports' screen. Click the 'Interim Transaction Reports' button in the 'Islamic Customer Accounts Detailed' screen to invoke this screen.

The screenshot shows a software dialog box titled "Interim Transactions Report". It features a blue header bar with a diamond icon and window control buttons. The main area is white and contains several sections of controls. On the left, there's a section titled "Interim Transactions Report" with two unchecked checkboxes: "Generate Message" and "Generate Message Only On Movement". Below this are two rows of controls: "Statement Count For The Day" and "Year To Date Statement Count", each with a text input field and a "Times" button. To the right of these are "Report Transactions Since" and "Of" dropdown menus. A second section titled "Account Balance" has a checkbox for "Generate Balance Report" and another "Report Transactions Since" and "Of" dropdown menu. At the bottom right, there are "Ok" and "Exit" buttons.

This screen contains the details necessary for the account generation parameters. The message details the balance of the customer account that is under a particular account class. The account balances indicate the condition of the customer account for an identified time period.

2.3.31 Specifying Interim Transactions Report

Generate Message

Check this box to indicate that the periodic interim statement (MT942) generation is required for the account. This will be defaulted from 'Account Class Maintenance' screen. However,

you can modify it. The 'Consolidated Statement' and 'Generate Message' are mutually restricted.

Generate Message Only on Movement

Check this box to indicate that the interim statement generation is required, only if additional entries have been posted subsequent to the previous interim statement generation. This will be defaulted from 'Account Class' screen, however you can modify it.

Report Transaction Since

This section lists all the transactions of the interim account statement, which are supposed to be reported. This will be defaulted from 'Account Class' screen, however you can modify it. You can choose the appropriate values applicable:

- Previous MT942 - This indicates that all transactions posted and authorized since previous MT942 would be sent in the current interim statement.
- Previous MT940 - This indicates that all transactions posted and authorized since previous MT940 will be sent in the current interim statement. If this option is selected, you will have to specify the cycle of account statement to be considered.

Minimum Debit Amount

Specify the minimum transaction amount for the debit transaction to be eligible for reporting in the interim statement. The corresponding amount for the account currency will be defaulted. However, you can modify the amount defaulted. If the amounts are not defined at the account class for the currency in which the account is being created, no defaulting of amounts shall be done.

Minimum Credit Amount

Specify the minimum transaction amount for the credit transaction to be eligible for reporting in the interim statement. However, you can modify the amount defaulted. If the amounts are not defined at the account class for the currency in which the account is being created, no defaulting of amounts shall be done.

Daily Statement Count

Specify the count of interim statement generated during the day. In case a statement is scheduled to generate, but is not generated because there is no movement, the counter will not be incremented. The counter will be reset at End of Day.

Year to Date Statement Count

Specify the count of interim statement generated for the account since start of the financial year. The financial year will be as defined in the Accounting Period maintenance. This counter would be set at the end of year.

Generate Balance Report

To indicate that the customer account is considered for generation of its balance message, check this box.

Of

Select the mode of message for balance generation from the option list.


Report Transaction Since

This section lists all the transactions the customer account has undergone, in the interval of balance messages generated for the account. You can choose the appropriate values applicable:

- Previous MT940: This indicates all transactions posted and authorized since the issue of a previous MT 940 in the current balance report
- Previous MT941: This indicates all transactions posted and authorized since the issue of a previous MT 941 in the current balance report

- Previous MT950: This indicates all transactions posted and authorized since the issue of a previous MT 950 in the current balance report

You can synchronize the time instance by hours for generation of the balance message by clicking the 'Times' button.



This screen is employed to indicate the the time instance in hours for the generation of the balance report.


Message generation time

Specify the timing for generation of the MT 941/ MT942 message. You can specify the time interval in hours only.

The details for issuing the balance reports are discussed in the chapter 'Maintaining Mandatory information, for different accounts under a particular class. The details involved in generation of a balance report for a specific customer account correspond with those discussed for account classes.

2.3.32 Specifying Notice Details

Notice preferences are maintained through the 'Notice Preferences' screen. Click the 'Notice Preferences' button in the 'Islamic Customer Accounts Detailed' screen to invoke this screen.



The following field is displayed in this screen:

Description

The following details are defaulted from the account class maintenance level. However, at the account level you are allowed to modify this.

Advance Profit

Check this field to levy the advance profit on the account

Note

- The customer is liable to pay this advance profit in case he/she fails to provide the required notice to the bank
 - The system deducts the advance profit from the credit profit earned by the customer on his/her credit balance in the account
-

Monthly Free Amount

Specify the amount that the customer can withdraw per calendar month from his/her savings account without being liable to pay advance profit.

Notice Days

Specify the number of days before which the customer should notify the bank if he/she wants to withdraw an amount more than the 'Free Amount' from his/her account.

Validity Period

Specify the validity period in number of days. During this period, the customer can do the withdrawal of the amount for which he/she notified the bank.

Note

This screen is applicable only for saving type of account

2.3.33 Specifying Cards Details

Card Summary details are maintained through the 'Card Summary screen'. Click the 'Cards' button in the 'Islamic Customer Accounts Detailed' screen to invoke this screen.

The screenshot shows a software window titled "Cards Summary Screen". At the top, there are three input fields labeled "Branch Code", "Customer No", and "Account Number". Below these is a table with the following columns: "Authorization Status", "Record Status", "Branch Code", "Request Reference Number", and "Card Number". The table contains one row with empty cells. At the bottom right of the window is an "Exit" button.

Here, you can view the following details.

Branch Code

The branch code is displayed from the main 'Customer Accounts Maintenance' screen.

Customer No

The customer identification code (CIF) of the account holder is displayed from the main 'Islamic Accounts Maintenance' screen.

Account No

The account number is displayed from the main 'Customer Accounts Maintenance' screen..

Authorisation Status

Indicate the authorisation status of the debit card by selecting one of the following values:

- Authorised
- Unauthorised

Record Status

Indicate the record status of the debit card by selecting one of the following values:

- Open
- Closed

Branch Code

The system displays the branch code where the debit card has been issued.

Request Reference Number

The system displays the request reference number of the card issuance record.

Card Number

The system displays the debit card number of the card holder.


Multiple cards can be issued to a customer.

2.3.34 Specifying OFAC Check Details

OFAC check enables the application to call an external web service to perform black list check for customer and customer accounts and give warnings appropriately while transacting with black listed customers. You can also capture your remarks before overriding the black list warning.

Click 'OFAC Check' button in 'Islamic Customer Accounts Detailed' screen to view the OFAC check response in the 'External System Details' screen. On clicking 'OFAC Check' button, system will build the request XML and call the web service. The 'External System details' screen displays the response is received from the external system and you will be also

allowed to enter your remarks in this screen. The response received will also be sent to Oracle FLEXCUBE Database layer for any further interpretations of the same.



The screenshot shows a dialog box titled "External System Details". It contains two text input fields: "External System Response" and "User Remarks". The dialog has a blue title bar with a diamond icon on the left and standard window controls (minimize, maximize, close) on the right. At the bottom right, there are "Ok" and "Exit" buttons.

Here, you can view /capture the following details:

External System Response

The response from the external system regarding the black listed customer is displayed here.

User Remarks

Specify your remarks regarding the black listed customer here.

2.3.35 Specifying Change Log Details

Change log details are maintained through the 'View'. Click the 'Change Log' button in the 'Islamic Customer Accounts Detailed' screen to invoke this screen.

The screenshot shows a software window titled "Authorize" with a close button (X) in the top right corner. The window is divided into several sections:

- Records:** A table with columns: Modification Number, Modification Status, First Authorization Status, Authorization Status, Maker ID, and Maker Date S. The first row contains: 1, N, A, Unauthorized, DOCUMENT2, 2012-11-07 2. Above the table is a navigation bar with "10f1" and a "Go" button.
- Remarks:** Four text input fields: "Maker Remarks", "Maker Override Remarks", "First Checker Remarks", and "Checker Remarks".
- Warnings:** A table with columns: Warning Code, Warning Description. A checkbox is present to the left of the header. Above the table is a navigation bar with "10f1" and a "Go" button.
- Fields:** A table with columns: Field Name, Old Value, New Value. A checkbox is present to the left of the header. Above the table is a navigation bar with "10f1" and a "Go" button.

At the bottom right of the window, there are three buttons: "Accept", "Reject", and "Cancel".

2.3.36 Maintaining Provisioning Preferences for a Islamic account

An account inherits the provisioning parameters defined for the Islamic account class it uses. You can change the defaulted parameters and make the following specifications, as required, in the Provision Details section of the 'Islamic Customer Accounts Detailed - Auxiliary' screen.

The screenshot displays the 'Islamic Customer Accounts Detailed - Auxiliary' screen. At the top, there are fields for Branch, Account, Currency, SD User Reference, Customer No, Customer Name, and Account Class. Below this is a navigation bar with tabs: Main, Auxiliary, Nominee, and Check List. The main area is divided into several sections:

- Positive Pay:** Includes checkboxes for Positive Pay, Funding, Mod 9 Validation Required, and Deferred Reconciliation. It also has fields for Stale Days, Fund Branch, and Funding Account.
- Provisioning Details:** Includes checkboxes for Auto Provisioning Required, Exposure Category, Risk Free Exposure Amount, and Provisioning Currency (Account/Local).
- Cheque Book Preferences:** Includes checkboxes for Auto Reorder of Cheque Book, Reorder Cheque Level, Reorder No of Leaves, Cheque Book Name 1, Cheque Book Name 2, and Max No of Cheque Rejections.
- Account Facilities:** Includes checkboxes for Cheque Book, Passbook, and CAS Account.
- Options:** Includes checkboxes for Euro Cheques, MT210 Required, Lodgment Book, Consolidated Certificate Required, Back Period Entry Allowed, Default Waiver, Mudrabah Sweep, Auto Deposit, Auto Cheque Book Request, and Auto Debit Card Request.
- Initial Funding:** Includes Account Opening Amount, Pay In Option (Pay In By Account/Pay In By GL), Offset Branch, Offset Account, and Waive account Opening Charges.
- Escrow Transfer Details:** Includes Escrow Transfer Applicable, Branch Code, Escrow Account, and Escrow Percentage.
- Passbook Details:** Includes Passbook Number and Passbook Status.
- ATM Details:** Includes ATM, Branch, ATM Account Number, Daily Amount Limit, and Daily count Limit.
- Intermediary Details:** Includes Intermediary Required and an Intermediary table with columns for Intermediary Code and Intermediary Description.

At the bottom, there is a navigation bar with links for Profit, Charges, Consolidated Charges, BIC, Deposits, Instructions, Standing Instructions, Linked Entities, Reg, Account Status, Restrictions, Currency Limits, MIS, Statement, Joint Holders, Fields, Deposits Instruction, Billing Parameters, Account Signatory, Interim Transactions Report, Notice, Cards, OFAC Check, Statistics, Cheque Book Request, Debit Card Request, Deposit Linkage, and Change Log. Below this is a status bar with fields for Maker/Checker, Date Time, Mod No, Record Status, and Authorization Status, along with an Exit button.

2.3.37 Maintaining Provisioning Percentages Details

In addition to the provisioning preferences listed above, you must also indicate the applicable provisioning percentage and the discount percentage details in the 'Provision Percentages'

screen that you can invoke by clicking the 'Provision' button in the Provisioning Details section of the 'Islamic Customer Accounts Detailed - Auxiliary' screen.

| Status * | Provision Percent | Discount Percentage |
|----------------------|----------------------|----------------------|
| <input type="text"/> | <input type="text"/> | <input type="text"/> |

You can maintain the following details here:

Provisioning Percentage

If you wish to indicate a specific provisioning percentage to be applicable for the account, you can specify it in the 'Provisioning Percentage' screen.

If you do not specify any provisioning percentage, the provisioning batch picks up the applicable provisioning percentage from the Exposure Provisioning Percentage Maintenance, for the exposure category of the account and the account status.

Discount Percentage

If you wish to indicate a specific discount percentage to be applicable for the account, you can specify it in the 'Provisioning Percentage' screen.

If you do not specify any discount percentage, the provisioning batch picks up the applicable discount percentage from the Exposure Provisioning Percentage Maintenance, for the exposure category of the account and the account status.

Viewing the Computed Provision Amount

The provision amount computed for the account is displayed in the Provision Amount field in the 'Amounts and Dates' button in the 'Islamic Customer Account Maintenance' screen.

2.3.38 Viewing details of Amounts and Dates

In the 'Amounts and Dates' screen you can view all Financial details of this customer's account along with the details of the previous debit or credit activities. However, access to all financial information of an account can be restricted for any user. The financial details of an account include the account balance, the un-cleared debit and credit balances, the debit and credit turnover and the profit details.

Click the 'Amounts and Dates' button in the 'Islamic Customer Accounts Detailed' screen.

2.3.39 Viewing Total Available Balance Details

The total available balance displayed by the System includes the unutilized line amount in case the customer enjoys an OD limit.

In the Amounts and Dates screen, you can view the outstanding debit profit and/or charges due on the account, as on the current date.

You can also view the amount that can be withdrawn against uncollected funds, on the account. The System computes the allowable amount based on the Withdrawable Uncollected Funds Basis option specified in the Branch Parameters Preferences screen.

2.3.40 Viewing Turnover Amounts

In the 'Customer Account - Turnover Amounts' screen you can view the total turnover of this customer account from the first date of this month to the current day's system date. Also, you

can view the accumulated profit associated with debit or credit transactions after the last liquidation.

To view the turnovers for the account, click the 'Turnover' button. The Customer Accounts - Turnover Amounts screen is displayed.

The screenshot shows a software window titled "Turnover". At the top, there are two tabs: "MTD - Account Currency" and "- Month to Date - LCY". Under the "MTD - Account Currency" tab, there are three rows of input fields, each preceded by the label "Dr". Similarly, under the "- Month to Date - LCY" tab, there are three rows of input fields, each preceded by the label "Dr". In the bottom right corner of the window, there is a button labeled "Exit".

After maintaining the required details you can return to the Amounts and dates screen.

2.3.41 Maintaining Other Details for Islamic Deposit Account

Using this screen, you can maintain the following details for Islamic Deposit Account:

- Maintain Credit Limit Liability details
- Maintain parameters for Joint Accounts
- Maintain Transaction Restrictions
- Maintain Account signatory details
- Maintain Account Statement details
- Specifying MIS details for an account
- Specifying payment and collection limits
- Specifying Regulation D applicability for a customer account
- Relationships for Customers

For further details, refer the chapter 'Maintaining Customer Accounts' in the Core Entities User Manual.

The screenshot shows a software window titled "Account Operating Instructions Maintenance". The window has a blue header bar with a diamond icon on the left and standard window controls (minimize, maximize, close) on the right. The main area contains several input fields and buttons. At the top left is "Date of Last Maintenance" with a text box. Below it is a section titled "Maintenance Instruction" with a horizontal line. Under this section are four rows for "Instructions (1)", "Instructions (2)", "Instructions (3)", and "Instructions (4)", each with a text box. Below these is a "Conditions" dropdown menu showing "1". Underneath is an "Elements" dropdown menu. Below that is an "Operators" dropdown menu and a "Value" text box. On the right side, there are four rows for "Conditions (1)", "Conditions (2)", "Conditions (3)", and "Conditions (4)", each with a text box. Below these are four buttons: "f", "y", "And", "OR", "Delete", and "P". At the bottom right of the window are "Ok" and "Exit" buttons.

The sign-on branch code is defaulted when you maintain a new instruction. The current system date is also displayed. You can select the customer account for which you want to maintain an operating instruction, from the available option-list.

On selection of the account, the description gets displayed in the adjacent field.

At the time of maintaining an instruction, you can also specify a condition for displaying the instructions when transactions pertaining to this account are being processed. The instruction will be displayed to you when the condition is satisfied.

2.3.42 **Closing a Islamic Account**

When you close an account the system will check whether an IP product linked to the account is pending liquidation. If an IP Product is pending liquidation you will be prompted to perform the liquidation before closing the account.

You can click on the Liquidate button to imitate the process whereby the system will calculate all outstanding amounts for all products involving the account and display the same. On confirming the details that are displayed the system liquidates the products. You will not be required to authorize this action.

If any provisioning has been done in respect of the account, the relevant amount is written back to the GL as specified in the maintenance, on Closure.

If the account does not have any IP products pending liquidation the system will display list of 'Close Out' modes in the 'Account Closure Details' screen.

In this screen you can select the Close Mode, which is to be used to close the account. The option list positioned next to this field contains a list of all the Close Modes maintained in the Customer Account Closing Modes screen. The product linked to the close mode will be defaulted.

Some of the close out modes may require additional details to complete the transaction. These additional details can pertain to either of the following:

- The Offset Account
- The Instrument (when the Close Out is through an Instrument) with which you payoff the balance in the account

Thus, based on the mode selected the withdrawal entries are booked against the appropriate product. The balance of the account will drop down to zero. Subsequently, the account is marked as closed.

For detailed information on the Customer Account Closing Mode Maintenance screen you can refer the Maintaining Customer Account Closing Modes sub-heading in Core Entities User Manual.

2.3.43 Executing Automatic Closure Batch

You can have all accounts for which the box 'Account set for closing' is checked automatically closed using a batch process after the profit distribution is completed. You need to configure this batch as a mandatory program in End of transaction Input (EOTI) stage using the

'Mandatory Batch Program Maintenance' screen. You can also configure it as an intraday batch.

You can invoke the 'Mandatory Batch Program Maintenance' screen by typing 'EIDMANPE' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The screenshot shows the 'Mandatory Batch Program Maintenance' window. It includes a toolbar at the top with 'New' and 'Enter Query' buttons. The main configuration area is divided into several sections: 'Branch *' and 'Module *' with input fields; 'Function Identification *' with 'Sequence Number' and 'Description' fields; 'End Of Cycle Group' with radio buttons for 'Transaction Input', 'End of Transaction Input', 'End of Financial Input', 'End of Day' (selected), and 'Beginning of Day'; 'Error Handling' with radio buttons for 'Stop Automatic End Of Day and Run Emergency Program' (selected) and 'Continue with Automatic End Of Day'; 'Frequency' set to 'Daily'; 'Holiday Rule' set to 'Do Not Execute'; 'Execution Layer' with radio buttons for 'Database' (selected) and 'Application'; 'Sub Stage' set to '1'; 'Number Of Days', 'Run Date', 'Job Code', and 'Description' fields. Below these is a 'Predecessors' section with a table containing one row labeled 'Predecessors *'. At the bottom, a 'Fields' section lists 'Input By', 'Authorized By', and 'Modification Number', each with a 'Date Time' field, and checkboxes for 'Authorized' and 'Open'.

This batch should be configured for execution after ICEOD batch.

Function Identification

Specify the function ID 'ICPDMBAT'.

End of Cycle Group

Choose 'End of Transaction Input'.

Frequency

Choose 'Daily' from the adjoining drop-down list.

After each profit distribution cycle, you will have to take a report of accounts where 'Account set for closing' is checked and then transfer the balance in such accounts in order to make the balance to zero for the purpose of automatic closure.

This batch will close all the applicable accounts after ensuring the following:

- Account balance is zero.
- Profit distribution is done.

- No more profit is accrued.

In case any of the aforesaid validations fail, the batch will not close the customer accounts. In case of such failure, the system will raise an exception.

2.3.44 Sweep In and Sweep Out Batch Processing

The Sweep In and Sweep Out process is handled by an EOD batch **STSWEEP**. All the utilized deposit accounts in a day are fetched by the batch **STSWEEP** due to CASA linkage. The amount block is then released to the CASA account by breaking the deposit.

Sweep In Process

During Sweep In Process the system:

- Releases the amount blocked for the deposit accounts for the utilized amount.
- Transfers the amount to relevant CASA account.
- Updates the deposit account balance.

Note

Other deposits are considered only after utilizing auto deposit created for account.

Sweep Out Process

During Sweep Out process the system:

- Check for the credit balance in the CASA account.
- Transfer the credit balance or the linked amount to the relevant deposit account.
- Updates the utilized amount for the transferred amount.

Note

Other deposits are considered only after utilizing auto deposit created for account.

2.3.45 Generating Alert for Secure Overdraft Utilization

Secure Overdraft (SOD) facility is given against collaterals for an account. Oracle FLEXCUBE facilitates generation of alert when SOD utilization is closer towards the consolidated limit amount of the collaterals.

Oracle FLEXCUBE runs a batch process to identify such breached SOD accounts and generates alerts as per the maintained percentage parameter at SOD account level and decides the breach limit for every account. The system sends the generated alerts as ADVICE format (email) or ASCII flat file. It defines the message format for email and captures the following key information to send these alerts to OD customer:

- Email ID
- Mobile number

The system runs a CASA batch adding the following process 'SODALERT':

- Identify the SOD accounts to be processed
- Read the percentage for breach calculation
- Identify if the breach happened

- Generate the alert to intermediate data store
- Generate the MSG handoff in case the medium is mail
- Complete the message generation if the medium is mail
- Update the dispatch flag as processed.

2.3.46 Creating a Message Advice Format

You need to create a message advice format through the 'Advice Format Maintenance' screen with the format named 'SOD_CR_UTIL'. You should also create an outgoing generic interface to generate ASCII file where in the component details for the generic interface are the elements from the new data store. You need to schedule this generic interface to be executed during EOD through 'GIDPRSIF' batch.

Note

The system processes alerts only if the email address and mobile number are maintained for a customer.

You can know the Limit Utilization Breach for the account by the application of the following formula:

'(Utilized limit amount) \geq (SOD Amount *SOD notification percentage) / 100'

The Intermediate data store consists of the following details:

- DCN
- BRN
- Customer Account Number
- Customer No
- Customer Mail
- Customer Mobile No
- Utilized Amount
- Overdraft Amount
- Dispatch Flag

You need to maintain the following message advice format through the 'Advice Format Maintenance' screen.

#RH

< SOD ACCOUNT UTILIZATION >

Date: _DATE_

Bank Name: _BANK-NAME_

Branch Address: _BRANCH-ADDR_

Customer Name: _CUST-NAME1_

Customer ID: _CUSTOMER_

Account Number: _ACCOUNT-NO_

OD Amount: _OD_AMOUNT_

Utilised Amount: _UTIL_AMOUNT_

#EH

#B

#SC

#IF _DIFFEQAUL_

Your Account with Account Number _ACCOUNT-NO_ has reached the limit of the OD.

#ENDIF

#IF _DIFFGREATER_

Your Account with Account Number _ACCOUNT-NO_ has breached the limit of the

OD by _DIFFGREATER_

#ENDIF

#EC

#EB

#RF

FOR _BRANCHNAME_

AUTHORIZED SIGNATORY.

#EF

For more information on Advice Format, refer 'Maintaining Advice Format' chapter under 'Messaging System' User Manual.

Note

For multiple collaterals you need to consider consolidated limit amount for deriving the breach limit amount.

The system re-uses the following key information for alert generation:

- Email ID – from customer personal maintenance
 - Mobile number – from CIF – personal information
-

2.4 Viewing Islamic Customer Accounts Details

You can view the Islamic customer accounts details maintained in the 'Islamic Customer Accounts Detailed' screen using the 'Islamic Customer Accounts Summary' screen. You can

invoke this screen by typing 'IASCUSAC' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The screenshot shows a web application window titled 'Summary'. At the top, there are 'Advanced Search' and 'Reset' buttons. Below these are search filters: 'Authorization Status' (dropdown), 'Record Status' (dropdown), 'Branch' (text input with a search icon), and 'Account' (text input with a search icon). Below the filters is a pagination bar showing 'Records per page 15' and '1 Of 1'. The main area contains a table with columns: 'Authorization Status', 'Record Status', 'Branch', 'Account', 'Account Description', 'Customer No', 'Currency', and 'Account C'. The table is currently empty. At the bottom right of the window is an 'Exit' button.

In the above screen, you can base your queries on any or all of the following parameters and fetch records:

- Authorization Status
- Branch Code
- Record Status
- Account

Select any or all of the above parameters for a query and click 'Search' button. The records meeting the selected criteria are displayed.

Note

You can query or modify the account details of the customers whose accounts are permitted to you for the query/modification in the 'Group Code Restriction' screen.

If you are allowed to query customer information, then system displays the following details pertaining to the fetched records:

- Authorization Status
- Record Status
- Branch Code
- Account
- Description
- Customer Number
- Currency
- Account Class
- No Debits
- No Credits
- Stop Payments
- Dormant
- Account Open Date
- Alternate Account Number

- Cheque Book
- Passbook
- Account Number
- Account Type
- IBAN Account Number
- Frozen

2.5 Changing Primary Party of an Account

You can change the primary customer of a specific account using 'Primary party Change Maintenance' screen. To invoke this screen, type 'IADCUSCH' in the field at the top right corner of the application toolbar and click the adjoining arrow button.

The screenshot shows a software window titled "Islamic Primary Party Change Maintenance Screen". At the top left, there is a "Save" icon. The main area contains several input fields:

- Account No * (with a dropdown arrow icon)
- Branch Code (with the value "000" entered)
- Customer No * (with a dropdown arrow icon)
- Name
- Remarks *
- Account Description
- Currency
- Account Class (with a "Populate" button next to it)

At the bottom of the window, there is a navigation bar with links for "Linked Entities", "Account Signatory", and "Customer Change Details". Below this is a status bar with fields for "Maker", "Checker", "Mod No", "Date Time:", "Record Status", and "Authorization Status". A "Cancel" button is located in the bottom right corner.

Specify the following details:

Account

Specify the account number for which you need to change the primary customer. The option list displays all valid active and open accounts under the current branch. Unauthorized and tanked accounts will not be available for selection.

Select the appropriate account number.

Description

Based on the account selected, the system displays the account description.

Branch Code

The system displays the current branch code.

Currency

The system displays the currency associated with the selected account.

Customer Number

The system displays the customer number of the primary customer of the account.

You can modify this and specify the customer number as per requirement. The option list displays all valid active and open customer numbers. Select the appropriate one.

The customer number that you select here must be different from the customer number displayed on selection of the account number.

Once you have selected the customer number, click 'Populate' button. The system will update the 'Account Signatory' and 'Linked Entities' details based on the changed customer number. If you do not click the 'Populate' button, on saving the record, the system displays an error message.

Customer Name

Based on the customer number, the system displays the name of the customer.

Account Class

The system displays the account class to which the selected account belongs.

Remarks

Specify your remarks related to the change of primary customer.

2.5.1 Viewing linked Entities

Click 'Linked Entities' button to view the linked entities.

When you click 'Populate' button after selecting the customer account, the system will update the changed customer as the primary account holder in 'Linked Entities' screen. The other details will remain the same. However, you can modify the details.

For further details on the 'Linked Entities' screen, refer to the section 'Specifying Linked Entities' in this chapter.

2.5.2 Viewing Account Signatory Details

Click 'Account Signatory' button to view the account signatory details.

When you click 'Populate' button after selecting the customer account, the system will update the account signatory details based on the changed customer.

If you have checked the box 'Replicate Customer Signature', then the system clears the signatures maintained for the old customer in the 'Account Signatory' sub-screen and displays the rest of the signatures. This may include signatures of the joint holders. The system will also default the signature maintained for the changed primary account holder.

If you have not checked the option 'Replicate Customer Signature', then the system clears the signatures maintained for the old customer.

For further details on the 'Account Signatory' details, refer to the section 'Specifying Account Signatory Details' in this chapter.

2.5.3 Viewing Customer Change Details

Click 'Customer Change Details' button to view the details of primary customer changes.

The screenshot shows a software window titled "Customer Change Details". At the top, there are two input fields: "Branch Code * 000" and "Account No *". Below these is a "Validate" button and a "Customer Change Log" tab. There are also "Validate" and "Report" buttons. An "Error Messages" section is visible, showing a table with columns "Error", "Error Type", and "Error Messages Maintenance". The table is currently empty. At the bottom right are "Ok" and "Cancel" buttons.

You can view the following details:

Branch Code

The system displays the branch code.

Account

The system displays the account number for which the primary account has been changed,

2.5.3.1 Validate Tab

From the 'Validate' tab, you can validate the customer changes and view the error/override messages. Click 'Validate' button. The system will display the following details if there is a possible error or override during the process.

Error Code

This is the error code for the error\ override message.

Type

This indicates whether the message was an error message or an override message.

Message

This field displays the details of the error/ override message.

The list will contain the details of possible errors in the beginning, followed by the possible overrides.

You can generate a report of the error/ override messages using the 'Report' button. Once you click this button, the system will display the 'Report Options' screen. Select the appropriate options and click 'OK' button to generate the report.

You can view the following details in the report:

Header

Under the Header, you can view the following details:

- Branch Code

- Account Number
- New Customer Number
- Old Customer Number
- Remarks
- Date and Time
- Maker Id

Detailed


Under detailed section, you can view the following details:

- Error Code
- Error Type
- Error Message

Based on the possible error information received, you can resolve such issues and proceed to save the customer change.

2.5.3.2 Customer Change Log Tab

Under this tab, you can see the history of all customer changes that has happened for the selected account.



In this tab, you can view the history of all customer changes happened on a given account. Against each customer change information, you can view all the overrides triggered during the change process.

This screen will display the details of unauthorized customer changes, if any. The authorizer can view the overrides and take a decision whether to authorize the change or not.

For each primary party change, you can view the following details:

- Date of change
- Old customer number
- New customer number
- Remarks entered by the user
- The user ID of the maker

- The user ID of the checker/authorizer
- The user ID of the verifier
- Whether the change has been authorised or not

For every selected change record, you can view the following details of the errors/ overrides:

- Error code
- The error/ override message

Once you have captured and verified all the details, save the record. If the new customer number is not different from the old one, then the system will display an error message.

Note

Note the following:

- Multi branch access is not supported for this operation.
 - This operation is considered as a customer account amendment. External notifications that exist for the customer account modification will continue to work for this.
 - If there is any unauthorized primary party change record, then the system will not allow amendment of that customer account.
-

The primary party change will be effected and updated in the customer account records only after authorization. During authorization, the system will repeat the validations. If there is any error, then you will not be allowed to authorize the record.

You need to manually handle the following situations:

- Any correction in the relationships maintained at customer account level using 'Primary Party Change' screen
- Modification of address at the account level
- Re-submission of mandatory documents as part of customer change
- Change in the ICCF product, rule or charge
- Change in the joint holders list or list of signatories required because of the customer change
- Customer spread
- Deactivation of ATM cards and debit cards
- Changes in the status of the customer or account due to primary party change
- Checking uninitiated transaction (transactions in external channels), upload tables, workflow stages. Validation of transaction in referral queue, ELCM queue and PC queue
- Validation of user defined status of account
- Issuance of new card to the new customer
- Validation of existing track receivables in the account
- Records for customer and account combination in the Service Request Screen (STDS-RQST)

You need to operationally handle the following changes:

- Joint holders
- Notice preference
- Escrow transfer details
- Currency limit details

- Document checklist
- Profit and charge subsystems
- Address details, location, media, country code, cheque book name
- Deposit instructions and other instructions
- Nominee details
- Restriction details
- Memo instructions
- Service request
- Statement details
- Interim transaction report details
- UDF details
- ATM details such as name on card
- KYC status
- Customer account tax allowance limit
- Check book re-order details
- Dormancy parameter details (STDSTDOR)
- Salary account flag
- Home branch of old and new customers
- Gender, resident status, staff, minor status
- Stop payment request maintained
- New cheque book requests, debit card requests, Debit card activation requests

Note

Note the following:

- Through relationship pricing it is possible to define different rates based on the eligibility criteria of the customer. After the customer change has been effected, the system evaluates the eligibility criteria and applies benefit plan. At this point, the system considers the relationships maintained for the new customer.
 - After the primary party change, AML tracking for online/daily TOV/monthly TOV for the customer group associated with the new customer takes place. On the same day, customer account entries will report to two customer numbers.
 - In case of back dated transactions in the account after primary party change, the system considers the new customer while passing accounting entries.
 - The system does not validate the origination accounts during primary party change.
 - Transactions in PC which are active at the time of primary party change will show the old customer number itself in the 'Payments and Collections Contract' screen.
 - The changes made using 'Primary Party Change' screen will not reflect in the change log of the customer account screen.
-

2.5.4 Viewing Islamic Primary Party Change Summary

You can view a summary of Islamic account primary party changes made in the system using 'Islamic Primary Party Change Maintenance Summary' screen. To invoke this screen, type

'IASCUSCH' in the field at the top right corner of the application toolbar and click the adjoining arrow button.

The screenshot shows a software window titled "Islamic Primary Party Change Maintenance Screen". At the top, there is a toolbar with buttons for "Search", "Advanced Search", "Reset", and "Clear All". Below the toolbar, there is a "Case Sensitive" section with four input fields: "Authorization Status" (a dropdown menu), "Record Status" (a dropdown menu), "Branch Code" (a text field with a search icon), and "Account No" (a text field with a search icon). Below these fields, there is a "Records per page" dropdown set to "15" and a "1 Of 1" indicator. The main area is a table with the following columns: "Authorization Status", "Record Status", "Branch Code", "Account No", "Account Description", "Account Class", and "Customer No". The table currently contains no data rows. At the bottom right of the window, there is an "Exit" button.

You can search for the records based on one or more of the following parameters:

- Authorization status
- Record status
- Branch code
- Account number

Once you have specified the parameters, click 'Search' button. The system displays the following details of all records that match the search criteria.

- Authorization status
- Record status
- Branch code
- Account number
- Account description
- Account class
- Customer number

Note

Following are some additional information related to primary party change.

- The system does not validate the usage of the account in the any retail transactions. Retail transactions includes following modules RT, UP, CG, IS and DE.
- If the account is used in corporate transactions, the system validates whether the account is maintained as a settlement account in any of the authorized or unauthorized contracts. If it is used, the system displays an override message listing the

transaction reference numbers. Corporate transactions include the transactions from the modules other than those mentioned above.

- After the primary party change, the customer balance report to the MIS codes of the new customer. For existing transactions, the related customer or customer in MIS will not change.

2.6 Viewing Mudarabah Sweep Details

You can view Mudarabah Sweep details in the Mudarabah Sweep History Details screen. You can invoke this screen by typing 'IADSWHIS' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows a software interface for viewing Mudarabah Sweep details. At the top, there are search criteria fields: Branch Code, Account Number, Account Currency, and Current Balance. Below these are two data tables. The first table, titled 'Mudarabah Sweep Details', has columns: Order of Linkage, Branch, Account Number, Linked Percentage, and Linked Amount. The second table, also titled 'Mudarabah Sweep History Details', has columns: Branch, Account Number, Operation (with a dropdown menu showing 'Sweep In'), Transaction Date, and Transfer Amount. An 'Exit' button is located at the bottom right of the window.

In the above screen, you can base your queries on the following parameters and fetch records:

- Branch Code
- Account Number

Select any or all of the above parameters for a query and click 'Search' button. The records meeting the selected criteria are displayed.

If you are allowed to query sweep details for the account, then system displays the following details pertaining to the fetched records:

- Order of Linkage
- TD Branch
- TD Account Number

- Linked
- Auto Deposit
- Linked Percentage
- Linked Amount
- Utilized Amount

If the Mudarabah Sweep detail is checked then the system displays the following sweep history for the customer account:

- TD Account Number
- Branch
- Operation
- Transaction Date
- Transfer Amount

3. Maintaining Investment Weights

3.1 Introduction

In order to compute the profit distribution on a *Mudarabah* fund, you need to capture the risk associated with every investment that forms the *Mudarabah* fund.

3.2 Maintaining Investment Weights

You can capture the risk or weight attached to every deposit investment in the 'Weights Maintenance' screen. This screen allows weights maintenance for different combinations of fund Id, product type, account class, effective date and currency. You can invoke the 'Weights Maintenance' screen by typing 'ICDWTMNT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Here you can specify the following details:

Mudarabah Fund Id

You can specify the *Mudarabah* Fund Id for which you wish to maintain deposit weight details from the option list. The option list contains all *Mudarabah* fund Id that are active and authorized.

Currency

You can specify the currency to maintain deposit weight details from the option list. The option list will displays all the currency codes maintained in the system.

Effective Date

You can specify the date from which the weights should be considered for profit calculation and distribution. You can also maintain a back-valued effective date but not a future date.

Account Class

You can specify the account class for which you wish to maintain weight details from the option list. The option list displays all the account classes linked to the selected fund Id.

Bank Local Currency

The system defaults the bank local currency here and not the Branch currency. The entire profit calculation will be done in this currency.

Product Type

The system will default the product type based on the account class selected on saving the record:

- Savings
- Current
- Term Deposits

3.2.0.1 Broken Period

Weight (%)

You can specify a weight in percentage that should be for calculating the profit when term deposits are redeemed before their maturity dates.

If the utilization amount is not zero at the end of PDM calculation period then the system considers the broken weightage maintained along with other weightages for deposits in Mudarabah Sweep.

3.2.0.2 Mudarib Fee

Fee (%)

You can specify a fee in percentage that should be used as *Mudarib* fee for profit allocation calculation for the given pool code, account class and currency combination.

3.2.0.3 Value Category

Amount Slab

You can assign a weight to an amount slab. For all investment wherein the amount falls in the particular slab, the weight specified against the slab will be applicable.

Weight (%)

You can specify the weight for an investment falling under the specified slab.

3.2.0.4 Tenor Category

Units

You can specify the frequency of the term deposit. You can choose from the following option available in the drop-down list:

- Months
- Year

Tenor

You can specify the tenor of the term deposit.

TD Weight

You can specify the weights for Investment accounts having the particular profit distribution frequency.

Savings/Current Account

You can specify the weight for savings accounts falling under the chosen *Mudarabah* fund Id. This field is available only if the product type is specified as 'Savings'.

Note

In this field you are not allowed to maintain the weight details for the TD and units, tenor and weight details will not be allowed to maintain for Savings and current account classes.

3.2.0.5 PPO Category**Days**

You can specify the profit distribution frequency in terms of days. You can specify any numerical value from 1 to 99.

Months

You can specify the profit distribution frequency in terms of months. You can specify any numerical value from 1 to 12.

Years

You can specify the profit distribution frequency in terms of number of years.

Weight (%)

You can specify the weights for investment accounts having the particular profit distribution frequency.

3.3 Profit Calculation Batch

You can calculate the profit and as well as initiating distribution to depositors and shareholders for the *Mudarabah* fund using 'Profit Calc Batch' screen. You can invoke the

'Profit Calc Batch' screen by typing 'ICDPRCBT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Bank Local Ccy

The system displays the local currency of the bank.

Financial Cycle

The system displays the previous month's financial cycle.

3.3.0.1 Period Code

From

You can specify the period code from which the profit needs to be shared. The option list displays all period codes maintained in the system. You can select the appropriate one.

To

You can specify the period code until which the profit needs to be shared. The option list displays all period codes maintained in the system. You can select the appropriate one.

Period Type

Specify the type of period for which the profit sharing needs to be done. You can choose any of the following options available in the drop-down list:

- Notional
- Actual

Mudarabah Fund ID

You can specify the fund id for which the profit calculation needs to be done. The option list displays all fund IDs for which the profit has to run for the period codes. However if the profit distribution is done already then the system will not display those fund IDs.

Profit Calc Sequence Number

When you click save icon, the system defaults the 'Profit Calc Sequence Number' in this field.

Profit Equalization Amount

You can indicate the following preferences.

Credit/Debit

Indicate whether the PEA amount should be deducted from or added to the depositor's profit. Select one of the following options:

- Credit - Choose this to add the PEA amount to the depositor's profit.
- Debit - Choose this to deduct the PEA amount from the depositor's profit.

Lcy

Specify the PEA amount (in local currency) that should be deducted from the depositor's profit before deduction of the *Mudarib* fee. If you have chosen 'Credit' as the PEA criterion, then indicate the amount that should be added to the depositor's profit. *Mudarib* fee will not be deducted in this case. Alternatively, if you have specified the PEA % for depositor's investment, the system will compute the PEA amount in local currency and display it here.

PEA% for DEP Investment

Specify the amount that should be considered for PEA deduction/addition, as a percentage of the depositor's profit. The PEA amount in local currency will be computed based on this figure. Alternatively, if you have specified the PEA local currency amount, the system will display the same as a percentage of the depositor's profit.

You can view details of the batch by clicking the 'View Profit Calc Log' button.

The batch needs to be authorised in order to be submitted.

While executing this batch, the system computes the balance of each account, based on the profit calculation balance basis maintained for the linked account class. The system computes the cash reserve amount for each account based on the cash reserve ratio (CRR) maintained for the currency in the linked account class. If the CRR value is not maintained for the currency, it will consider the CRR specified for the account class a whole. It deducts the computed cash reserve amount from the account balance before applying weights in profit distribution.

The system considers the account balance after deduction of cash reserve ratio for depositor's investment in profit sharing.

3.4 Updating Profit Calculation

You can view the details of all account class using 'Profit Calc Update' screen by selecting a record, the system populates all the details. You can invoke the 'Profit Calc Update' screen

by typing 'ICDPRUPD' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The following details will be populated in the screen:

Account Class

The system displays the account class to which the deposit accounts belong. You cannot modify it.

Madarabah Fund ID

System will display the Mudarabah fund id to which the selected account class is linked.

From Period Code

The system displays the period code from which the profit needs to be shared (Previous Months Period code).

To Period Code

The system displays the period code until which the profit needs to be shared (Previous Months Period code).

Financial Cycle

The system displays the previous month's financial cycle.

Period Type

The system displays type of period for which the profit sharing needs to be done. It can be any of the following options:

- Notional
- Actual

Product Type

The system displays the type of product. It could be either 'Savings' or 'Deposit'.

TD Type

If the accounts belong to a Term Deposit account class, the system will display the account type (Broken /Normal).

Account Ccy

The system displays the currency in which the investment account is maintained.

Amount Slab

The system displays the maximum limit of the Investment amount to make up the slab.

Tenor

The system displays the tenor of the deposits falling under the amount slab in terms of months. For savings, the tenor is displayed as 1 month.

PPO

The system displays the profit pay out frequency of the Investment falling within the amount range and tenor in terms of days, months or year. The frequency is shown in the following format: 'nnnDnnMnnY' where 'n' stands for a numerical value.

LCY Amount Before Weights

The system displays the LCY equivalent amount of the total account class contribution before applying the applicable weightages.

Weights

The system displays the weighted average balance of the deposits in the amount range and tenor.

LCY Amount After Weights

The system displays the depositors' value in a particular account class in LCY after application of weights.

Profit Amount Before Fee

The system displays the profit amount accrued to the deposits in the amount range and tenor, before fee application.

***Mudarabah* Fee %**

Your bank recovers some expenses by way of a *Mudarib* fee which will be recovered as a percentage of the fund profit. The system defaults this value from the 'Weights Maintenance' screen.

***Mudarabah* Fee LCY**

The system displays the local currency equivalent value of the *Mudarabah* fee charged for the account class with currency.

Adj *Mudarabah* Fee LCY

Specify the *Mudarabah* fee in local currency.

Profit After *Mudarabah* Fee ADJ

The system displays the total profit for a particular account class and currency combination, after the *Mudarabah* fee adjustment (if any) on saving.

Ann. Rate after *Mudarabah* Fee ADJ

The system computes the annualized profit rate based on the profit amount and the deposit value and displays it here.

Adhoc ADJ Amt

You can make an adhoc adjustment which affects the annualized percentage of profit. Specify the adjustment amount here.

Profit Amt after ADHOC ADJ

The system displays the total amount of profit distributable to the account class after doing the adhoc adjustment.

Ann. rate after ADHOC ADJ

The system indicates the annualized percentage of profit after doing the adhoc adjustment.

Annualized Rate Before ADJ in %

The system displays the Annualized rate before the before the Mudarib fee, PEA and Adhoc adjustment.

ADJ Annualized Rate in %

The system displays the final adjusted value of the annualized percentage after *Mudarib* fee, PEA and Adhoc adjustment (Non Editable).

3.5 Profit Distribution Batch

Profit sharing for a *Mudarabah* fund is primarily driven by the weights ratio between depositors and shareholders in the fund. As mentioned before, the weights for deposits are maintained in the 'Weights Maintenance' screen. You can capture the weight for shareholders and also compute the profit for depositors and shareholders in the 'Profit Distribution Batch' screen. You can invoke the 'Profit Distribution Batch' screen by typing 'ICDPRACT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'LBL_PROFIT_DISTR_BATCH' application window. It features a top navigation bar with 'New' and 'Enter Query' options. The main area is divided into several sections:

- Period Code:** Includes 'From *' and 'To *' input fields.
- Bank Local Currency:** An input field.
- Financial Cycle *:** An input field.
- Period Type *:** A dropdown menu currently set to 'Actual'.
- Mudarabah Fund Id *:** An input field with a 'Populate' button below it.
- Total Investment:** A list of input fields for 'PEA GL', 'IRR GL', 'Share Holders', 'Depositors', 'Total', 'PEA GL', 'Share Holders ADJ', 'Total Adjusted', 'Weights in %', 'Effective Weights %', and 'Profit Distributable for Depositors'.
- Total Profit:** A list of input fields for 'Total', 'Profit Adjusted', 'Profit After ADJ', 'Share Holders', 'Depositors', 'Total PEA ADJ Amount', 'Depositors Profit After PEA', 'Total Fee Amount', 'Depositors Profit After Fee', 'Total Ad hoc Adjustment Amount', and 'Depositors Profit After IRR'.
- Profit Equalization:** Includes radio buttons for 'Credit' (selected) and 'Debit', an 'LCY' input field, and a 'PEA % for Depositor Investment' input field.
- Investment Risk Ratio:** Includes radio buttons for 'Credit' (selected) and 'Debit', a 'Local Currency' input field, and an 'IRR' input field.
- Profit Apply Sequence Number:** An input field.
- View Profit Apply Log:** A button.

The bottom of the window contains a footer area with fields for 'Maker', 'Checker', 'Mod No', 'Date Time:', 'Record Status', and 'Authorization Status', along with an 'Exit' button.

You can capture the following details in this screen:

3.5.1 **Period Code**

From

The system displays the previous month's period code from which the profit needs to be shared.

To

The system displays the previous month's period code until which the profit needs to be shared.

Bank Local Ccy

The system displays the local currency of the bank.

Financial Cycle

The system displays the previous month's financial cycle.

Period Type

Specify the type of period for which the profit sharing needs to be done. You can choose any of the following options available in the drop-down list:

- Notional
- Actual

***Mudarabah* Fund ID**

You can specify the fund id for which the profit calculation to be done from the option list. The option list displays all fund Ids for which the profit has to run for the period codes. However if the profit distribution is done already then the system will not display those fund Ids.

Click the 'Populate' button, to view the record for the combination of the data entered in the 'Profit Cal Update' screen. If there is any unauthorized record the system will not populate the record.

3.5.2 **Total Investment**

Here you can capture the following details:

PEA GL

The system displays the balance of the PEA GL for the *Mudarabah* fund. This amount is computed on the basis of the liability GL (specified as PEA) that is linked to the particular *Mudarabah* fund id in the '*Mudarabah* Profit Calculation Maintenance' screen.

IRR GL

The system displays the balance of IRR liability GL. This balance is computed based on the 'Profit Contribution Balance Basis' specified in the 'Islamic Profit Calculation GL Maintenance' screen.

Share Holders

On selecting the *Mudarabah* fund id, the system displays the total investment of the fund as contributed by the shareholders, in this field. This amount is computed on the basis of all the liability GLs that are linked to the particular *Mudarabah* fund id. The system arrives at this amount based on the preference set in the 'Profit Contribution Balance Basis' field in the '*Mudarabah* Profit Calculation Maintenance' screen for the selected *Mudarabah* Fund ID. If the balance basis is not maintained for that GL in the Linkage screen, the system will consider the preference set in the '*Mudarabah* fund Share Holder Balance Type' field 'Bank Parameters - Preferences' screen.

Depositors

On selecting the *Mudarabah* fund id, the system displays the total investment of the fund as contributed by the depositors, in this field. The system arrives at this amount based on the preference set in the 'Profit Contribution Balance Basis' field in the 'Account Class Maintenance' screen for the account class to which the particular *Mudarabah* fund id is linked.

Total

On selecting the *Mudarabah* fund id, the system displays the total investment of the fund in this field.

Weights in %

Specify the weight (as a percentage of the total shareholders' investment) that should be used to compute the profit for shareholders. The system shows a default value of '100%'. However, you can change it.

EFF WTS %

Once the shareholders' weight is specified, the system displays the effective weight of the shareholders as a percentage of the total shareholders' investment.

PEA GL ADJ

You can specify the adjustment amount posted to the PEA GL contribution.

Share Holders ADJ

You can specify the adjustment amount posted to the shareholders' contribution.

Total ADJ

The system displays the sum of the Shareholder, Depositor and PEA contribution after adjustment.

Profit Distributable to Depositors

The system deducts the PEA from the depositors' share of profit (minus the *Mudarib* fee) and displays it here.

3.5.3 Total Profit

Here you can capture the following details:

Total

The total profit for the *Mudarabah* fund is calculated from the income/expense type GLs linked to the particular *Mudarabah* fund in the '*Mudarabah* Profit Calculation Linkage' screen.

Profit ADJ

You can specify the total profit adjustment amount.

Profit After ADJ

The system displays the total amount less the profit adjustment.

Share Holders

The system computes the total profit for shareholders based on the effective investment ratio calculated earlier and displays it here.

Depositors

The system computes the profit share for depositors based on the effective investment ratio.

Total Fee Amount

System display the Total *Mudarabah* fee amount calculated for the Depositor accounts. *Mudarib* fee percentage will be taken from the weight maintenance screen maintained for account class

Depositor's Profit After Fee

The system deducts the *Mudarib* fee amount from the depositors' share of profit and displays it here.

Total PEA ADJ Amount

System display the total PEA Adj amount made for the depositor in the 'Profit Calc Update' screen.

Depositor's Profit After PEA

The system deducts the PEA amount from the depositors' profit fit and displays the net amount here.

Total Adhoc ADJ Amount

The system sums up the adjustment amounts made for the depositors and then displays the total adjustment here.

Depositor's Profit After IRR

The system displays the depositors profit after deducting the Investment Risk Reserve (IRR) amount.

3.5.4 Profit Equalization Amount

Specify the following details.

Profit Equalization Amount

If credit is selected then the Amount specified in the LCY field and Percentage mentioned in the PEA % for dep investment will be added to the total depositor profit amount (in case of loss amount will be debited from the PEA GL & distributed to the depositor).

If Debit is selected then the Amount specified in the LCY field and Percentage mentioned in the PEA % for dep investment will be deducted from the total depositor profit amount (In the months that your bank makes more-than-expected profit, you can set aside some profit as 'Profit Equalization Amount'. You can use this amount to distribute to the depositors in the months of losses).

Lcy

You can also specify the PEA as a fixed amount in the bank's local currency.

PEA % for DEP Investment

In the months that your bank makes more-than-expected profit, you can set aside some profit as 'Profit Equalization Amount'. You can use this amount to distribute to the depositors in the months of losses. Specify the PEA as a percentage of the depositors' profit.

Investment Risk Reserve

Specify the following details.

Credit/Debit

Indicate whether the IRR amount should be deducted from or added to the depositor's profit. Select one of the following options:

- Credit - Choose this to add the IRR amount to the depositor's profit.
- Debit - Choose this to deduct the IRR amount from the depositor's profit.

Lcy

Specify the IRR amount that should be deducted from the depositor's profit after allocation of PEA and before deduction of the *Mudarib* fee. Alternatively, if you have specified the IRR%

for depositor's investment, the system will compute the IRR amount in local currency and display it here when you click the save icon.

IRR%

Specify the amount that should be considered for IRR deduction/addition, as a percentage of the depositor's profit. The IRR amount in local currency will be computed based on this figure. Alternatively, if you have specified the IRR local currency amount, the system will keep this field blank. After specifying the IRR local currency, even if you specify a value here, the system will make it blank upon clicking the save icon.

Profit Apply Sequence Number

When you click the save icon, the system defaults the 'Profit Apply Sequence Number' in this field.

When you click the authorise icon, the system will re-calculate the profit distributable to Shareholders and depositors and also the system will recalculate the profit and post the final adjustment amounts and the profit rates applicable to the individual accounts will be propagated.

Note

- No more changes are allowed in the 'Profit Distribution Batch' screen, once the batch is submitted. With Period type as 'Notional' you can do what if analysis (*Mudarabah* Rate will not be propagated).
 - Once the Batch is submitted with 'Actual' Period type Derived *Mudarabah* Rate will be updated to the individual account with effective date as the start date of the period.
-

3.6 Profit Calculation Exclusion Batch

You can invoke the 'Profit Calculation Exclusion Batch' screen by typing 'STDREXBT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows a software window titled "Profit Calculation Exclusion Batch". At the top left, there are two buttons: "New" and "Enter Query". Below these are two input fields: "Period Code" and "Financial Year", each with a small dropdown arrow icon to its right. Underneath these fields is a blue button labeled "Populate Parameters". Below that is an "Intraday Sequence Number" input field, followed by a blue button labeled "Submit Batch". At the bottom left of the window is a blue button labeled "View Log".

Specify the following details:

- Period Code

- Financial Year
- Intraday Sequence Number

3.7 Zakat Batch Process

The *Zakat* processing batch needs to be run for all the savings accounts for which the 'Zakat Exemption' option is unchecked in the 'Customer Accounts Maintenance' screen. You can run this batch through the 'Zakat Processing Batch' screen. You can invoke this screen by typing 'ICDZAKBA' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Here you can capture the following details:

IP Product

Specify an IP product maintained for *Zakat* computation. The adjoining option list displays all the IP products maintained in the system. You can select the appropriate one from there. Also, you can select 'All' and execute batch for all *Zakat* products.

You can run this batch on the First Day of *Ramadan*. On execution of this batch process, the *Zakat* will be automatically calculated and deducted from the accounts to which the chosen IP product is linked. If this batch is re-run on the same date, then the accounts where *Zakat* has already been liquidated will not be charged again.

If the batch is run after a day, the computation will take place on the *Ramadan* date.

3.7.1 Status Change Batch Processing (CSDSTBTC)

For the IA module the Status change batch will be run along with the customer/Group and apply worst status change for the customer. This batch will use the status change events.

You can trigger the batches to run before the Common Status Change batch (CSDSTBTC). The following given batches can be run in any order:

- LCEOD
- BCAUSTCH
- CLBATCH
- ICEOD

- CIDBATCH
- MODBATCH
- CASABAT
- IAAUTDLY
- CSDSTBTC
- ICEOD
- CLDPROV
- MODPROV
- CIDPROV

If 'Status Processing' is at Individual Contract Level, then system will trigger status change based on the Customer Credit rating for the customer of the Contract /Account booked. The other contracts of the customers in the same Group will not be impacted. However if the 'Status Processing' is at CIF/Group level individual module (LC,CL, CI, MO, CA, IA and BC) batches will be updating common storage with the derived status of each contract and CIF/ Group level status will be triggered by the common status change batch. The common status change batch will call the individual module function for status change processing.

4. Creating Islamic Term Deposits

4.1 Introduction

Any deposit with a fixed term or tenor is referred to as a Term Deposit (TD). To handle a TD in Oracle FLEXCUBE, you need to:

- Set up a suitable account class
- Set up a suitable IP product
- Maintain a TD account
- Define Profit Conditions and other parameters for the deposit account

Additionally, you need to maintain the following details for operating a Term Deposit (TD):

- Instructions
- Payin Parameters
- Closing Mode

4.2 Maintaining Term Deposit Account Class

To handle term deposits in Oracle FLEXCUBE, you have to set up an account class of type 'Deposit', in the 'Islamic Account Class Maintenance' screen. You can invoke the 'Islamic Account Class Maintenance' screen by typing 'IADACCLS' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot displays the 'Islamic Account Class Maintenance' application window. The interface includes a top navigation bar with 'New' and 'Enter Query' buttons. The main content area is organized into several sections: 'Account Details' (Account Class, Description, Account Type, Start Date, End Date), 'Statement Parameters' (Account Code, Dormancy Days, Account Statement Format, Display IBAN in Advices, Inter Pay, Natural GL, Dormancy Parameters, Applicable Customer Status), 'Provisioning Details' (Provisioning Frequency, Provision Currency, Exposure Category, Event Class Code, Escrow Transfer Applicable), 'Debit Profit/Charge Liquidation' (Liquidate Using Receivable, Verify Funds, Debit Notice, Liquidation Days, Liquidation Mode), and 'Initial Funding' (Transaction Code, Transaction Code For Reversal, Cash Deposit Limit on Trust Account, Event Class Code, Charge Role To Head Code). A bottom status bar contains fields for 'Maker', 'Checker', 'Date Time', 'Mod No', 'Record Status', and 'Authorization Status', along with an 'Exit' button.

Refer the section 'Maintaining Islamic Account Class' in the chapter 'Creating Islamic Accounts' of this User Manual for details about setting up an account class.

Note

Typically, for every deposit scheme you offer at your bank, you would set up a Deposit Type Account Class.

4.2.1 Specifying Deposit Preferences

Click the 'Deposit' button to define the parameters for a deposit type account class. The 'Deposit Account Details' screen will be displayed.

The screenshot shows the 'Deposit Account Details' window with the following sections and options:

- General Options:** Rollover, Close On Maturity, Allow Partial Liquidation, Allow Partial Liquidation With Amount Block, Move Profit To Unclaimed, Move Principal to Unclaimed, Month-end Maturity Deposit, Re-pick up Account Class Tenor On Rollover.
- Grace Period for Renewal:** Reference Date (calendar icon), Auto Extension, Allow Prepayment.
- Rate Chart Deposits:** Rate Chart Allowed, Rate Chart Tenor (dropdown).
- Cluster Identification:** (dropdown).
- Deposit Amount Currency wise Limits:** Table with columns: Currency, Min Amount, Max Amount.
- Holiday Treatment:** Holiday Calendar (Ignore), Holiday Movement (No Change), Maturity Date Movement Across Months (No Change In Maturity Date), Adhoc Holiday Change (No Action), Applicable Deposit Tenor (dropdown).
- Minimum Tenor:** Days, Months, Years (input fields).
- Default Tenor:** Days, Months, Years (input fields).
- Maximum Tenor:** Days, Months, Years (input fields).
- Recurring Deposit:** Recurring Deposit, Move Maturity to Unclaimed, Move funds on Override.
- Installation Frequency:** Days, Months, Years (input fields), Maximum Schedule Days (input field).
- Redemption:** Redemption (dropdown), Pre Redemption (dropdown), Profit Sharing.

Buttons: Ok, Cancel.

Indicate the following details:

Allowing Auto Rollover of Deposits

You can opt to automatically rollover a deposit if it is not liquidated on its maturity date. Choose the 'Auto Rollover' option to automatically rollover deposits opened under the account class. Term deposits that are open and marked for Auto Rollover will automatically be rolled over during the Beginning of Day operations on the Maturity date. You can define the terms and conditions for the new deposit while maintaining the deposit account in the 'Details for Deposit Type Account' screen.

Close on Maturity

Check this field to close the term deposit account on maturity date and transfer the amount to the principal liquidation account. If you select this option, the principal liquidation account should be an account other than the term deposit account.

Month-end Maturity Deposit

Check this box to indicate that the deposit is a month-end maturing deposit, i.e., the deposit matures on the last working day of the month.

If this box is checked at the account class, then during deposit input, if the account opening date is the last working day of the month and the maturity date is the last day of the subsequent month, then you need to specify tenor in Months. If this box is un-checked, then

the deposit is not considered as an month-end maturing deposit even though the deposit is opened on the last working day of the month and the tenor of the deposit is across months.

During TD opening, a deposit is considered as a month-end maturing deposit only if the following criteria are met:

- The start date of the deposit is the last working day of the month
- The tenor of the deposit is across months
- The 'Month-end Maturity Deposit' box should be checked

An account class with 'Month-end Maturity Deposit' box checked can also have deposits that are not month-end maturing deposits. A deposit is classified as an ordinary deposits (not month-end maturing deposit) if the following criteria are met:

- The deposit is not opened on the last working day of the month
- The tenor of the deposit is across months but not month-end maturing
- The deposit is opened on the last working day of the month, but the tenor is in Months and Days.

Note

- For month-end maturing deposits, holiday movement and movement across months is not applicable.
 - During rollover, the deposit maturity date will be the last day of the month and if it is a holiday as per the applicable holiday calendar, then the maturity date movement is not applicable for month-end maturing deposits.
-

Auto Extension

You can specify whether prepayment needs to be allowed for the deposit accounts before the maturity date of the deposit. However, if this option is not checked, the system will not allow you to redeem the term deposit before the maturity date.

The system also allows you to indicate whether the deposit created on this account class has to be extended to one more tenure (principal only). If you check this, the term deposit will be closed on maturity, after the completion of the extended tenure.

4.2.1.1 Defining Specifications for Unclaimed Deposits

On the maturity date of a deposit, you can opt to:

- Liquidate the deposit
- Rollover the deposit
- Move it to an 'unclaimed' GL

Profit for the term deposits liquidated during the specified schedules is handled in two ways:

- If a customer account has been specified, profit is moved to the account during each liquidation event
- You can opt to move the profit to an 'Unclaimed profit GL'. When claimed, the profit can be paid out of this GL

Similarly, on maturity, the principal can be moved to specified Principal Liquidation Account, if specified, or to an Unclaimed Principal GL.

Note

- If you select the Move to Unclaimed GL option, this specification takes precedence. That is, on maturity, the funds will be moved directly to the respective Unclaimed GLs.
 - If 'Move to Unclaimed' is opted, then payout is not mandatory
 - The Unclaimed profit and Principal GLs are specified while maintaining an profit and Charges (IP) Deposit Type product. The Accounting Roles for the GLs are 'INT_UNCLAIMED' and 'PRN_UNCLAIMED' respectively. When maintaining an IP-Deposit type product, you have to map these Accounting Roles to the appropriate GLs maintained at your bank.
-

4.2.1.2 Rate Chart Allowed

Check this box to indicate that the system should calculate TD interest based on the LDMM float rate maintained in the 'LD MM Floating Rate Input' screen (CFDFLTRI). If you check this box, the system will pick interest rates based on different tenors, amount slab, currency and effective date for a TD. The rate is picked up at the time of booking. The rate is further picked up only at the time of liquidation/ rollover/ redemption operations based on repopulation flag at IC product level.

You will not be able to modify this preference once the record is authorised.

4.2.1.3 Deposit Amount Currency wise Limits

Deposit amount currency wise limits:

- Currency - Specify the currency for which the minimum / maximum / top-up units to be defined. The option list displays all active currencies maintained.
- Minimum amount - Specify the minimum amount for which deposit should be created under this account class. If the TD account is booked below the minimum amount then the system displays an error message: "Deposit amount is less than the minimum amount at account class".
- Max amount - Specify the maximum amount for which deposit can be created under this account class. The system will display a configurable override if the deposit amount contravenes the specified amount range or if the maximum amount is not specified.

4.2.1.4 Re-pick up Account Class Tenor On Rollover

If you check this box, the rollover tenor will be defaulted as 'Account Class tenor' at TD account. During rollover the default account class tenor will be picked up.

You can change this preference anytime during the life cycle of TD. On changing this and saving the record, the system displays a configurable override message "Re-pick account class tenor on rollover restrictions exists at account class".

4.2.1.5 Maintaining Holiday Treatment Details

Specify the following details:

Holiday Treatment

Holiday Calendar

Select the holiday calendar applicable to the account class from the adjoining drop-down list. This list displays the following values:

- Ignore - Select this option to ignore all other holiday parameters for the account class. By default, this option is selected
- Branch - Holiday calendar will be based on the branch holiday maintenance of the respective branch
- Currency - Holiday calendar will be based on the currency holiday maintenance done at bank level for the respective currency
- Both Branch & Currency - Holiday calendar is based on both branch and currency holiday maintenance

The holiday calendar is used to arrive at the maturity date. The holiday calendar defined at the account class is applicable to all term deposits under the account class. You cannot modify the 'Holiday Calendar' if there are active accounts under the account class.

- Both Branch & Currency

For month-end deposits, if holiday calendar is applicable, then the account class holiday calendar options indicate the following:

- Ignore - Maturity date does not change even if it is a holiday, i.e., the maturity date will be last day of the month. If you select this option, then system ignores all other values.
- Deposit Branch Holiday - If the maturity date is a holiday as per the deposit branch calendar, then system moves the maturity date to the last working day of the same month.
- Deposit Currency Holiday - If the maturity date is a holiday as per the deposit currency calendar, then system moves the last working day to the same month.
- Both Deposit Currency and Branch Holiday - If the maturity date is a holiday as per the deposit currency and branch calendars, then system moves the maturity date to the last working day of the month.

Holiday Movement

Select the working day to which the holiday should be moved from the adjoining drop-down list. This list displays the following values:

- No Change - If you select this option, then there is no change in the maturity date. Also, system ignores the value selected for 'Maturity Date Across Months'. By default, this option is selected.
- Previous Working Day - In case the computed maturity date is a holiday, then system moves the maturity date to the previous working day for the corresponding Holiday Calendar chosen.
- Next Working Day - In case the computed maturity date is a holiday, then system moves the maturity date to the next working day for the corresponding Holiday Calendar chosen.

Holiday movement is adjusting the next maturity date when the maturity date falls on a holiday, based on the Holiday Calendar chosen. 'Holiday Movement' is not applicable if you select 'Ignore' option for 'Holiday Calendar'.

Note

You cannot modify the 'Holiday Movement' if there are active account under the account class.

Maturity Date Movement Across Months

Select the maturity date movement across months from the adjoining drop-down list:

- Allowed - If the computed maturity date falls on a holiday, then the maturity date can be moved to the next/previous working day even it falls in a different month based on the Holiday Movement option.
- Previous/next working day of the same month - If the adjusted maturity date falls on the previous/next month, then the system moves the maturity date forward or backward to the next or previous working day of the same month.
- No change in maturity date - If the adjusted maturity date falls on next/ previous month, then the system ignores the movement and considers the computed maturity date as the maturity date even it falls on a holiday.

Maturity date across months is applicable only when the maturity date is adjusted to previous or next working day.

System displays an override message in the following cases:

- When allowed, the maturity date is moved across months
- when the maturity date is re-adjusted to the last working day of the month
- When the calculated maturity date is used in case the maturity date movement to the next month is not allowed

Whenever there is a change in the maturity date, system changes the rollover maturity date accordingly.

System ignores the value of 'Maturity date movement across months' if you select the 'No Change' option for 'Holiday Movement'.

Adhoc Holiday Change

Select the adhoc holiday change from the adjoining drop-down list. The adjoining drop-down list displays the following values:

- Change Maturity date and generate advice - System updates the maturity date and the rollover maturity date as per the TD holiday calendar maintenance, generates an advice to the customer.
- Generate Advice - System generates an advice on deposits having maturity date falling on a holiday.
- No Action - There will not be any change in the maturity date. The system does not generate any advices for the TD if this option is selected. By default, this option is selected.

The adhoc holiday change is the change in branch and currency holiday calendar after opening the TD due to adhoc change in holiday or branch transfer of the deposit. System ignores the value of 'Adhoc Holiday Change' if you select the 'Ignore' option for 'Holiday Calendar'.

Applicable Deposit Tenor

Select the deposit tenor, applicable to the deposit for interest rate pick-up, from the adjoining drop-down list. This list displays the following values:

- Original Tenor - If you select this option, then system considers the tenor which is defaulted from the account class or modified at the account level. By default,
- Deposit Tenor - If you select this option, then system considers the tenor based on the adjusted maturity date.

Note

On saving a deposit, if there is a change in maturity date due to holiday treatment, then system displays the revised tenor as the deposit tenor due to the revision in maturity date.

4.2.1.6 **Defining Redemption Details**

Indicate the following preferences.

Profit Sharing

You can opt to consider all *Mudarabah* deposit accounts under this account class for *Mudarabah* profit-sharing purpose. If you wish to achieve this, check the option 'Consider for Profit Sharing'. Once this option is checked, the profit sharing for *Mudarabah* deposit is done.

If 'Consider for Profit Sharing' is opted, then it is mandatory to specify the *Mudarabah* fund Id in Preferences sub-screen.

Redemption

A deposit can be redeemed in two ways at maturity:

- Principal component alone
- Principal and profit components

You can choose the appropriate option from the following values displayed in the drop-down list:

- Principal
- Principal+Profit

For all *Mudarabah* deposits that are considered for profit-sharing, the system allows only principal redemption on the maturity date. The deposits remain in the 'Active' status till the next profit distribution date. The profit is liquidated into the deposit only the next date of profit distribution.

Pre-Redemption

In case of *Mudarabah* deposits that are redeemed before maturity, you can indicate the components that should be paid at the time of redemption. You can choose from the following values displayed in the drop-down list:

- Principal
- Principal+Profit

For such *Mudarabah* deposits, on the date of redemption the system re-computes the profit for the period for which the profit has already been paid, using broken period rate. It then deducts the computed amount from the *Mudarabah* deposits principal amount. The system then credits the reduced principal amount to the payout account.


The deposit remains in the 'Active' status till the next profit distribution date from the date of redemption.

In the case of premature redemption, the profit gets liquidated only after the profit calculation and distribution has happened for that financial cycle. This is done by checking 'Defer

Liquidation' option in the 'Islamic Profit Distribution Product' screen. The profit will finally get liquidated into the Payout account maintained.

4.2.2 Specifying the Auto Deposits

You can create an auto deposit in case the balance in the source account exceeds a certain threshold. The auto creation of deposits is carried out as an end of day process. Click 'Auto Deposits' button in the 'Islamic Account Class Maintenance' screen and invoke the following screen.



For creating an auto deposit, you have to maintain the following parameters:

Account Class

For creating an auto deposit, you have to specify an account class of the deposit. The tenor and profit conditions maintained for the selected account class will be defaulted.

Note

- You cannot create an auto deposit if the Account class you have chosen has expired, that is, surpassed the end date maintained for the account class. The system will log an exception in such a case.
-

Transaction Code

You have to specify the transaction code for the auto creation of the deposit.

Currency

Mention the currency in which the deposit is created.

Minimum Required Balance

The minimum balance indicates that only the amounts above this limit will be used for auto creating deposits. You have to specify the minimum amount that the customer can retain in the account.

Deposit Multiple Of

For an account you can indicate the amount, which will be the basis for the deposit amount wherein the deposit amount will be in the multiples of the amount you specify here.

Def Rate Code

Select the code of the differential rate from the adjoining option list

Def Rate Type

Select the type of differential rate code; whether 'Mid' or 'Buy' or 'Sell'.

Break Deposits First

Check the box to indicate whether you want the funds to be moved by breaking deposits before breaking the deposit accounts. If you leave the box unchecked, the funds will be moved first from the linked CASA accounts.

Sweep Mode

You can indicate the pattern in which sweep outs are created by selecting any one of the two options:

- Auto – Here the amounts are automatically swept out at the end of day when minimum balance exceeds.
- Manual – You have to manually initiate the sweep. The sweep will execute only those instructions that are specified while account opening/ad hoc.

Break Method

You can choose to maintain any one of the following order of breaking deposits:

- LIFO (Last In First Out)– Indicates that the last created deposit will be broken first
- FIFO (First In First Out) – Indicates that the Earliest Deposit will be broken first
- MAXB (Maximum Balance) – Indicates that the Deposits are broken in descending order of available balance
- MINB (Minimum balance) – indicates that the order of breaking of Sweep / Auto deposit will be done for the Account / Deposit with the Minimum Balance

Provide Profit on Broken Deposits

You have to specify whether you want to provide profit on deposits that were broken prematurely. Check the box to indicate that you want to give profit for the deposits. Leave it unchecked to indicate otherwise.

4.3 Setting Up Profit Preferences for TD

You need to set up a Profit/Charge product to handle the calculation of profit and charges on a TD. You can set up a product using the 'Islamic Profit Distribution Product Maintenance' screen, invoked from the Application Browser. You can invoke the 'Islamic Profit Distribution

Product Maintenance' screen by typing 'IADPRMNT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Profit & Charges Product Maintenance

New Enter Query

Product Code *
Product Description *
Product Type
Description
Slogan
Product Group
Product Group Description
Start Date
End Date
Remarks

Include For TDS Calc
 Deposit
 Tax
 Billing Liquidation

Charge Basis
Description
Booking Account Type: Profit
Rule
Rule Description

Accounting Roles | Events | Branch | Customer | Preferences | Status Maintenance

Maker
Checker
Mod No

Date Time:
Date Time:
Record Status
Authorization Status

Exit

4.3.1 Linking TD Account Class to Profit Product

You can link the TD Account Class to the Profit product in the 'Profit Preferences' screen. Click 'Preferences' button on the 'Islamic Profit Distribution Product Maintenance' screen and invoke the following screen.

The screenshot shows the 'Profit Preferences' dialog box. It includes fields for 'Product Code', 'Description', and 'UDE Currency' (set to 'Account Currency'). There are three tabs: 'Profit' (selected), 'Charges', and 'Consolidated Charges'. The 'ILM Parameters' section includes 'ILM Product' (checkbox), 'ILM Type' (dropdown), 'Product Level' (checkbox), 'Accrual Day' (0), 'Frequency' (Daily), and 'Cycle' (None). The 'Debit Profit Notification' section includes 'Receivable General Ledger' (dropdown), 'Reallocation Through Header' (checkbox), and 'Payment Method' (radio buttons: Bearing, Discounted). The 'Calculation and Liquidation' section includes 'Days', 'Months', and 'Year' (all 0), 'First Liquidation On:' (dropdown), 'Start Date' (field), 'Liquidation at Month Ends' (checkbox), 'Back Value Recalculation Flag' (checkbox), 'Defer Liquidation' (checkbox), 'Defer Liquidation Days' (0), 'Liquidation Before Month End' (checkbox), 'Defer Before Month End Days' (0), and 'Zakat Product' (checkbox). The 'Account Details' section features a table with columns: 'Account Class', 'Description', 'Currency', 'Special Condition Only', 'Rate Change on Profit Liquidation', and 'Rate change on'. The table is currently empty. At the bottom right are 'Ok' and 'Cancel' buttons.

Here you can specify preferences for profit calculation and application on the accounts to which this product is applied.

Account Details

You can indicate the TD accounts on which this product should be applied.

Account Class

Specify the account class of 'Deposit' type that you have maintained for creating TDs. The adjoining option list displays all valid account classes maintained in the system. You can select the appropriate one.

All TDs created under this account class will inherit the profit parameters maintained in this screen.

Continue Variance on Rollover

Check this box to enable continued variance on rollover. If you check this, then the system will default account variance as current value to the rollover deposit for the next cycle

If you do not check this, then the account variance will not be carried forward to next rollover cycle

The field Continue Variance on Rollover cannot be modified at the product level after the first authorization.

Refer the chapter 'Creating an Islamic Profit Distribution Product' in this User Manual for details about setting up the product.

4.4 Creating Islamic TD

You can create a term deposit account using the 'Islamic TD Accounts Maintenance' screen. To invoke this screen type 'IADCUSTD' in the field at the top right corner of the Application tool bar and click the adjoining arrow button.

Specify the following details.

Branch Code

The system displays the branch code of the sign on branch.

Term Deposit Account Number

The system creates a unique reference number to identify the TD account number and displays it here, on saving the record.

Term Deposit Currency

Specify the currency of the TD. A list of all the currencies maintained in the system is displayed in the available option list. You can select the appropriate one.

SD User Reference

The system displays the SD user reference for the TD accounts.

Customer No

If you have included the CIF Number of the customer as part of the Account Mask, the system automatically defaults the CIF code of the customer in the respective field. You will not be allowed to modify this code.

However, while defining the Account Mask in the Account Parameters section of the Bank-wide Parameters screen, if you have specified that the CIF Number should not be a part of the account mask you will have to specify the customer code manually. A list of all the valid customer codes is displayed in the available option list. You can select the appropriate.

Customer Name

On entering the Customer No, the customer name is automatically displayed.

Account Class

In Oracle FLEXCUBE, you can classify the customer accounts of your bank into different groups. Each group is referred to as an account class and is maintained in the Account Class Maintenance screen. For each class, you have to define certain common attributes applicable to all accounts in the particular class.

While maintaining a specific account you have to identify the class to which the particular account belongs. You can select the appropriate account class from the list of all the valid account classes maintained in the system. Account classes that have surpassed their end date (expired) will not be displayed in the option list.

Details maintained in this screen are classified into four tabs:

| | |
|-----------------------|---|
| Main | Here you maintain the main attributes of the TD like the account number, customer code, the account class, account currency, type of account - single or joint, account status etc. |
| Nominee | Here you can capture nominee details for the TD. |
| Deposit | Here you specify deposit-specific details. |
| Dual Currency Deposit | In this tab, you can maintain details of a dual currency deposit. |

4.4.1 Main Tab

By default, the 'Main' tab is displayed when you invoke this screen. The fields in the Main section are as follows:

Description

This is the description of the account. Here you can enter the nature of the account like current, savings, overdraft, and so on. If a customer has two or more accounts under one account class you can specify the purpose of that account.

Account type

You have to indicate whether the account is to be opened only by the account holder or whether it can be jointly operated.

Fund Id

Select the fund id of the fund to be considered for report generation from the adjoining option list. The system defaults the value of Default Mudarabah Fund as fund id.

Country Code

To define the country limits for each individual country you have to select the country code from the option list available.

Mode of Operation

Select the mode of operation from the drop-down list.

Account Open Date

You have to capture the date on which the account was opened.

Alternate Account Number

You have to define an alternate account number for the account you are defining. The alternate account number that you specify should be unique for each customer. You can capture the old account numbers used by your bank before installing the Oracle FLEXCUBE system. The old account numbers would be mapped with the new account numbers. This would facilitate quick tracking of the account and generating queries.

In the Data Entry Module, you can input a transaction using the alternate account number instead of the actual account number.

Clearing Bank Code

The clearing bank code for the customer account is generated automatically if you have opted for auto generation in the Branch parameters

Clearing Account Number

The clearing account number for the customer account is generated automatically if you have opted for auto generation in the Branch parameters. The account number is created according to the account mask you have maintained for the branch. This will be mandatory, and has to comply with length of 9 characters and MOD 11 validation, if the value of the UDF 'Clearing A/C Mandatory' is maintained as YES in the Field Name to Value Definition screen.

However, you can choose to change this number here and the system validates this number with the account mask you have maintained for the branch

IBAN Account Number

To capture the detail of the IBAN account for a specific customer, you have to enable the 'IBAN Required' option by enabling it. Subsequently, click the 'M' button. The IBAN details sub-screen will be displayed.

In this screen, you can capture the IBAN Account Number as well as the bank code of the bank where the IBAN account resides.

Address

Specify the address of the customer.

Location

An address for a customer account is based on the 'Location' and 'Media' combination. Location codes maintained through the 'Account Address Location Type Maintenance' screen are made available against this field. The address maintained here is always the primary or the default address. Each customer can have several addresses for a particular media. To distinguish between one address of a customer from another for a given media, it is essential for you to specify a unique location for each address. Also, if you are amending an address here, the same gets updated in the 'Customer Account Address - Detailed' table after the validations are through.

Media

Select the media to communicate account related details to the customer, such as account maintenance related charges, fees, profit etc. from the option list. You can choose either of the following:

- Mail
- Telex
- SWIFT
- Fax

Linked Deposit Branch

Specify the linked deposit branch.

Linked Deposit Account

Specify the linked deposit account.

Zakat Exemption

When an account is opened in a branch, you need to clarify with the customer whether he or she will pay *Zakat* or will seek exemption. Check this box to indicate that the customer seeks exemption from *Zakat* charge.

Options

Indicate the following preferences.

Track Receivable

During liquidation of finance contracts as well as processing of retail teller contracts, if the system detects insufficient funds in the settlement account, then you can choose to block the subsequent credit that happens to the settlement account. In other words, the system will track the account for receivables (credits). As and when a credit happens, the funds will be allocated to the finance or retail teller contract, for liquidation. If the track receivable option is checked for the account, the system will track the receivables for the account if sufficient funds are not available in the account.

The allocation of funds will happen in a sequence that you specify at the account class level. This is explained in the section titled 'Maintaining Account Classes'.

Replicate Customer Signature

The signature of the customer gets defaulted from the account class level to account level. This value is defaulted only if the customer type is individual with single mode of operation.

Intermediate**Intermediary Required**

Check this box to link Intermediaries with Term Deposit.

Intermediary Code

Specify the intermediary code from the adjoining option list.

Intermediary Description

The system gives a brief description about intermediary code.

Intermediary Ratio

Specify the ratio of individual intermediary contribution against the Term Deposit account.

4.4.2 Nominee Tab

Click 'Nominee' tab in the 'Islamic TD Accounts Maintenance' screen. The following tab will be displayed.

The screenshot shows the 'Islamic TD Accounts Maintenance' application window. The 'Nominee' tab is selected. The form includes the following fields and sections:

- Search:** New, Enter Query
- Account Information:** Branch *, Account *, Currency *, SD User Reference
- Customer Information:** Customer No *, Customer Name, Account Class *
- Navigation:** Main, **Nominee**, Check List, Deposit, Dual Currency Deposit
- Nominee Details:** Name, Date of Birth, Relationship, Address 1, Address 2, Address 3, Address 4, Guardian Name, Relationship, Address 1, Address 2, Address 3, Address 4, Minor
- Footer Menu:** IP Special Condition | Charges | Linked Entities | Restrictions | MIS | Statement | Joint Holders | Fields | Account Signatory | TD Payout Details | Statistics | Rollover History | Change Log
- Footer Fields:** Maker, Checker, Date Time, Mod No, Record Status, Authorization Status, Exit

Specify the following details:

Name

Specify the name of the nominee.

Date of Birth

Specify the date of birth of the nominee.

Relationship

Specify the relationship of the nominee with the customer.

Address 1 to 4

Specify the address of domicile of the nominee. Four lines have been provided for this. Each line can have a maximum of 105 alphanumeric characters.

Minor

Check this box if the nominee is a minor.

Guardian Name

If the nominee is a minor, specify the name of the guardian.

Relationship

Specify the relationship of the guardian with the minor.

Address 1 to 4

Specify the address of domicile of the guardian. Four lines have been provided for this. Each line can have a maximum of 105 alphanumeric characters.

4.4.3 Deposit Tab

Click 'Deposit' tab on the 'Islamic TD Accounts Maintenance' screen. The following tab will be displayed.

Specify the following details:

Profit Start Date

Specify the date from which the profit accruals of TD account begins.

Deposit Tenor

The system calculates the tenor of the deposit account to the difference between Interest start date and Maturity date and displays it. In case of change in maturity date, the system changes the deposit tenor.

Note

System validates that the deposit tenor is within the minimum and maximum tenor allowed for the account class. If this validation fails, then system displays the error message, "Roll-over tenor does not fall in the range of minimum and maximum tenor allowed".

You can modify the default tenor during the following:

- Deposit account opening
- Any time before maturity during the life cycle of the deposit
- On rollover of the deposit

If you specify the tenor, the system computes the maturity date. If the maturity date computed by the system falls on a holiday, then the system will adjust the maturity date as per the holiday treatment maintenance at Account Class level and update the new tenor.

Once the record is authorized, you cannot amend the tenor.

The deposit tenor is represented in terms of years, months and days. For example, if the deposit tenor is 185 days, it should be represented as 0 years, 6 months and 5 days. If you select independent tenor, the you need to specify the values in the appropriate fields.

Years

This indicates the number of years in the deposit tenor.

Months

This indicates the number of months in the deposit tenor.

Days

This indicates the number of days in the deposit tenor.

Original Tenor

This indicates the original tenor of the deposit. You cannot change the original tenor displayed. The system displays the default tenor or the tenor specified at account which is arrived before the holiday movement

The original tenor is represented in terms of years, months and days. For example, if the deposit tenor is 185 days, it should be represented as 0 years, 6 months and 5 days.

Years

This indicates the number of years in the original tenor.

Months

This indicates the number of months in the original tenor.

Days

This indicates the number of days in the original tenor.

Maturity Date

The system defaults the maturity date from the default tenor from the account class. However, you can modify this date. On this date the term deposit account gets.

Auto Rollover

Check this field to automatically rollover the deposit you are maintaining. You have to indicate 'Rollover Type' on selecting this option

Close on Maturity

Check this field to close the term deposit account on maturity date and transfer the amount to the principal liquidation account. If you select this option, the principal liquidation account should be an account other than the term deposit account.

Move Profit to Unclaimed

Check this field to move the profit amount to the unclaimed GL mapped at the IP product in the accounting roles on maturity date of the term deposit account. If you select this option, the principal liquidation account should be the term deposit account.

Move Principal to Unclaimed

Check this field to move the principal amount to the unclaimed GL mapped at the IP product in the accounting roles and liquidate the profit amount to the profit booking account on maturity date of the term deposit account. is moved and is liquidated. If you select this option, the principal liquidation account should be the term deposit account

Term Deposit Amount

Specify the amount, which is paid for the time deposit account in the account currency.

If you have specified the percentage in the Pay-In options, on clicking the 'Compute' button, the system computes the amount. And while saving, the system validates the sum of Pay-In Amounts against the 'TD Amount' keyed in.

Note

The system will validate for the following:

- The deposit amount should be equal or greater than minimum booking amount maintained at the 'Deposits Cluster Maintenance' screen, else the system will display the error message: as, "The deposit amount is less than the minimum booking amount."
 - The deposit amount should be a multiple of the booking unit maintained at the 'Deposits Cluster Maintenance' screen, else the system will display the error message: as, "The deposit amount must be in multiples of booking unit."
-

Computed Amount

System displays the computed amount here.

Next Maturity Date

On selecting the rollover for the TD account, the system defaults the next maturity date from the previous tenor of the deposit.

The display of next maturity date is based on the rollover tenor selected.

Rollover Tenor

Indicate the rollover tenor for the TD account. You can select one of the following options:

- Account class tenor - If you select this, the rollover tenor in days, months and years is set to null. You cannot modify this. The system will not display the next maturity date, as the default account class tenor is subject to change. During rollover, the system updates it as the default account class tenor at the time of rollover.
- Account tenor - This is the default value. If this option is selected, the system populates the original tenor of the parent TD as the rollover tenor. The system displays the tenor in days, months and years. You cannot modify this. The next maturity date will be populated by adding the account tenor to the maturity date of child TD.

- Independent tenor - If you select this, you can specify the deposit tenor in days, months and years. The default value of the independent tenor will be null. The next maturity date will be populated by adding the independent tenor to the maturity date of child TD.

The tenor specified should be within the minimum and maximum tenor specified at account class. The tenor in months cannot be greater than 11 months. If tenor months are specified, then tenor days cannot be greater than 30 days.

The account tenor is defaulted as the deposit and rollover tenor for the child TD after the account class is populated.

Years

Specify the number of years in the rollover tenor.

Months

Specify the number of years in the rollover tenor.

Days

Specify the number of years in the rollover tenor.

Rollover Type

Select the rollover type. The following options are available.

- Principal
- Principal + Profit
- Special Amount
- Profit

Rollover Amount

If a special amount is to be rolled over, you have to specify the amount (less than the original deposit amount) in this field.

Stock Catalogue Code

The system displays the Stock Catalog Code of the TD certificate number.

Certificate Number

The system displays the TD certificate number in Deposit Tab.

Duplicate

This box remains checked if the certificate number issued is duplicate for this account.

Payin Details

You can view the following details of the deposit:

Term Deposit Pay-in Option

Indicate the method for initial funding during account creation. Choose one of the following options:

- Pay In By Account
- Pay In By GL

Note

The purpose of 'Cash' option in IADCUSTD screen is that when a user creates an Islamic TD account using the web branch (IPTDMM) screen by providing pay-in option as 'Cash', then the same account can be queried using the IADCUSTD screen. The pay in will be

displayed as 'Cash' for that account as maintained in the IPTDMM screen. Thus, the 'Cash' pay in option can be used only for querying an IPTDMM (web branch) account.

Percentage

Indicates the percentage of the amount to be deposited

Amount

Specify the amount being deposited to open a customer account.

Offset Branch

The system populates the branch code of the account from which fund is transferred to TD account.

Offset Account

Specify the account number/ GL from which the fund is transferred to TD account. This field returns the branch code if the account is selected and NULL is returned if GL is selected. If it

is Pay-In mode in GL then the system displays only GLs and if the Pay-In mode is Account then only accounts are displayed in the option list.

Recurring Deposit

Specify the following details:

Auto Payment Take Down

Check this field to allow the recurring deposit account to debit the payment account for the payment amount as per the installment frequency.

Move Maturities to Unclaimed

Check this field to move all the funds, on the maturity date, to the unclaimed GL mapped to the accounting role in the IP product.

Payment Branch

Specify the details for the branch to which the payment account belongs.

Payment Accounts

Specify the Payment Account; this can be either savings account or the current account from which the installment for the Recurring Deposit is collected as per the installment frequency

Installment Amount

Specify the installment amount that has to be collected from the payment account as per the installment frequency. This installment amount should be greater than the minimum amount mentioned at the account class.

Recurring Deposit Account

Check this field to indicate recurring deposit account.

Payment Date

Specify the date on which the payment needs to be done for recurring deposit account.

Payment Currency

Specify currency of the payment amount.

Note

- The system enables the offset account and branch detail fields only if the option to pay is selected as the savings account.
 - The Unclaimed Profit and Principal GLs are specified while maintaining an Profit and Charges (IP) Deposit Type product. The Accounting Roles for the GLs are 'INT_UNCLAIMED' and 'PRN_UNCLAIMED' respectively. When maintaining an IP-Deposit type product, you have to map these Accounting Roles to the appropriate GLs maintained at your bank.
 - The system allows you to select 'Close on Maturity' box, only when you specify the recurring deposit details. You have to maintain deposit transaction code as 'DPN' redemption transaction code as 'RED' and prepayment transaction code as 'TRF' for the recurring payments in the Branch Parameters for the Profit and Charges.
 - All recurring deposit payments are part of IP batch beginning of day activity.
-

Installment Frequency

Specify the following details:

Move funds on Overdraft

Check this option to indicate whether the Recurring Deposit account funds should move to an unclaimed account if it is overdue

Days

Specify the installment frequency in terms of days.

Months

Specify the installment frequency in terms of months.

Years

Specify the installment frequency in terms of years.

4.4.4 Dual Currency Deposit Tab

Click 'Dual Currency Deposit' tab on the 'Islamic TD Accounts Maintenance' screen. The following tab will be displayed.

The screenshot displays the 'Islamic TD Accounts Maintenance' application window. The 'Dual Currency Deposit' tab is selected. The form includes the following fields and sections:

- Header:** 'New' and 'Enter Query' buttons.
- Input Fields:** Branch *, Account *, Currency *, SD User Reference, Customer No *, Customer Name, Account Class *.
- Navigation:** Main | Nominee | Check List | Deposit | **Dual Currency Deposit**
- Main Section:** Dual Currency Deposit
 - Linked Currency
 - Currency Option Product
 - Option Contract Reference
 - Exchange Rate
 - Linked Currency Settlement Account
 - Linked Currency GL
 - Fixing Days
 - Yield Enhancement
 - Inception Fair Value
- Footer:** IP Special Condition | Charges | Linked Entities | Restrictions | MIS | Statement | Joint Holders | Fields | Account Signatory | TD Payout Details | Statistics | Rollover History | Change Log
- Bottom Bar:** Maker, Checker, Date Time, Mod No, Record Status, Authorization Status, Exit button.

Specify the following details:

Dual Currency Deposit

You can capture the following details for the deposit.

Linked Currency

This option is defaulted from the account class. However you can modify this value.

Currency Option Product

Specify the currency option product from the option list under which the Options Contract has to be created in case of Dual Currency Deposit. The option list displays all the Option Products with Product Type 'CO'.

Note

You need to mandatorily specify this product if the 'Linked Currency' is entered. You will be allowed to capture this value here only if the option 'Dual CCY Deposit' is checked at the 'Account Class Maintenance' screen. You will be allowed to modify this value even after authorization.

On saving the account, system validates the following to ensure that the currency option product selected here has the below features:

- Contract type is Trade
- Option Type is Call
- Deal Type is Buy
- Option Style is Plain Vanilla
- Barrier is not allowed
- Delivery type is Physical
- Expiration Style is American

Option Contract Ref No.

Specify the option contract reference number.

Exchange Rate

Specify the exchange rate of the currency.

Linked Currency Settlement A/c

Specify the settlement account of the linked CCY. Alternatively, you can also select the settlement account from the adjoining option list. This settlement account is used if the settlement has to take place in the Linked CCY, at maturity.

Linked Currency GL

Specify the GL used for posting the settlement entries in the linked currency. The adjoining option list displays all valid GLs maintained in the system. You can select the appropriate one.

Fixing Days

Specify the number of days from TD maturity date before which the exchange rate has to be fixed. This will be defaulted from the 'Account Class Maintenance' screen. However you change it. Note that fixing days cannot be lesser than zero or greater than the tenor of the TD.

Yield Enhancement

Specify the additional percentage of yield that the customer receives for agreeing on a currency Option.

Inception Fair Value

Specify the market value of the option contract at inception. This option is defaulted from the linked Options contract.

4.4.5 Check List Tab

Click 'Check List' tab on the 'Islamic TD Accounts Maintenance' screen. The following screen will be displayed.

The screenshot displays the 'Islamic TD Accounts Maintenance' application window. At the top, there are 'New' and 'Enter Query' buttons. Below these are search fields for 'Branch *', 'Account *', 'Currency *', 'SD User Reference', 'Customer No *', 'Customer Name', and 'Account Class *'. A navigation bar contains tabs for 'Main', 'Nominee', 'Check List', 'Deposit', and 'Dual Currency Deposit'. The 'Check List' tab is active, showing a 'Document List' table with columns: 'Document Type', 'Mandatory', 'Expiry Date', and 'Expected Date of Subm'. Below the table are 'Upload', 'Delete', and 'View' buttons. The 'Document Notification Details' section includes a 'Send Notification' checkbox, a 'Frequency' dropdown menu, and a 'Days' input field with '(Reminder)' text. A 'Remarks' section with a text area is also visible. The bottom of the window features a navigation bar with links like 'IP Special Condition', 'Charges', 'Linked Entities', 'Restrictions', 'MIS', 'Statement', 'Joint Holders', 'Fields', 'Account Signatory', 'TD Payout Details', 'Statistics', 'Rollover History', and 'Change Log'. The footer contains fields for 'Maker', 'Checker', 'Date Time', 'Mod No', 'Record Status', and 'Authorization Status', along with an 'Exit' button.

Specify the following details:

Document Type

Specify the document type. The adjoining option list displays all the document types that are maintained in the system. You can select the appropriate one.

Mandatory

Check this box to indicate that the document specified here is mandatory.

Expiry Date

Specify the expiry date of the document provided by the customer.

Note

- Expiry date will always be greater than 'Expected Date of Submission' and 'Actual Submission Date'.
 - Expected Date of Submission will always be greater than current date.
-

Expected Date of Submission

System displays the expected date on which the customer is accepted to submit the required documents.

Actual Submission Date

Specify the actual date on which customer has submitted the required documents.

Document Reference

System defaults the document reference here.

Checked

Check this box to indicate that the received documents are acknowledged.

You cannot save and authorize an account if the mandatory documents are not confirmed as 'Checked'.

Upload

Click on this button to upload the selected document type.

Delete

Click on this button to delete the selected document.

View

Click on this button to view the selected document.

Notification Details

System defaults notification details from the 'Account Class Maintenance' screen.

Send Notification

This check box indicates whether to send notifications or reminders for not submitting the mandatory documents.

Frequency (Notification)

System defaults the frequency of notification to be sent. The frequency can be one of the following:

- Daily
- Weekly
- Monthly
- Quarterly
- Half yearly
- Yearly

EMBED MSPhotoEd.3 - Note the following:

- Notification will be sent only if,
 - The check box 'Send Notification' is checked in Account Class Maintenance' screen.
 - The account status is active and authorized.
 - The mandatory documents are not submitted.
- Notifications will be sent based on the frequency specified.
- First notification will be sent on the expected date of submission or expiry date
- If notification date falls on a holiday then system will send the notification on next working day.

Days (Reminder)

System defaults the number of days left for the expiry or submission due date of the documents for sending the reminder.

System will send the following reminders:

- Reminder prior to the submission due date of the document.
- Reminder prior to the expiry date of the document.
- Overdue notifications after the due date if the document is not submitted based on the frequency.
- Notifications after the expiry date if the document is not submitted after the expiry date.

Note the following:

- Reminder will be sent only if,
 - The mandatory documents are not submitted.
 - The account status is active and authorized.
- Reminder will be sent only once.
- If reminder date falls on a holiday then system will send the notification on next working day.
- Reminder will be sent prior the number of days specified at the account level from expected date of submission or the expiry date.
- If there are more than one notifications or reminders of the same message type for which the notification schedule date falls on the same day for the same account, a single notification will be sent which will have the details of all the related documents.

Remarks 1 to 10

Specify the additional information, if required.

4.4.6 Capturing Additional Details

You can capture additional details for the TD by clicking the following buttons in the 'Islamic TD Accounts Maintenance' screen:

| Button | Function |
|-----------------|---|
| Profit | This invokes the 'IP Special Conditions Maintenance' screen. |
| Charges | This invokes the 'Account level charges conditions' screen. |
| Linked Entities | This invokes the 'Linked Entities' screen. |
| Restrictions | This invokes the 'Products and Transaction Codes Restriction' screen. |
| MIS | This invokes the 'Management Information System' screen. |
| Statement | This invokes the 'Statement Details' screen. |
| Joint Holders | This invokes the 'Linked Entities' screen |
| Fields | This invokes the 'User Defined Fields' screen. |

| | |
|-------------------|--|
| Account Signatory | This invokes the 'Signatory Details' screen. |
| TD Payout Details | This invokes the 'Term Deposit Payout Details' screen. |
| Rollover History | This invokes the 'Rollover History' screen. |
| Change Log | This invokes the 'View' screen. |

Note

In Rollover History, for Rollover Type, P = PRINCIPAL, I = PRINCIPAL + PROFIT, T = PROFIT and S = SPECIAL AMOUNT.

For further information on Additional details, refer 'TD Additional Details' chapter of 'Term Deposits' User Manual.

4.4.7 Specifying IP Special Condition Details

To define profit and other parameters for a TD, click the 'IP Special Condition' button in the 'Islamic TD Accounts Maintenance' screen. The 'IP Special Conditions Maintenance' screen is displayed.

The screenshot shows the 'IP Special Condition' maintenance window. It is divided into several sections:

- Account Details:** Includes fields for Branch (000), Account, Calculation Account, Profit Booking Account, Charge Booking Account, Profit Statement (checkbox), Consolidated Charge Account, Profit Start Date, Charge Start Date, Profit Booking Branch, Cr Advices (checkbox), and Charge Booking Branch.
- Product Details:** Includes fields for Product Code, UDE Currency, ILM Product (checkbox), and ILM Product Type.
- Effective Date:** A table with columns for Effective Date and Open. The first row is checked and has a date field.
- UDE Values:** A table with columns for User Defined Element Id, UDE Value, Rate Code, TD Rate Code, and Variance. The first row is checked and has input fields.

At the bottom of the window are 'Ok' and 'Cancel' buttons.

In this screen, you can specify the following TD related preferences:

Profit Booking Account

Specify the account into which profit on the TD should be booked for the customer.

Continue Variance on Rollover

The system defaults it based on the Profit and Charges product. However, you can modify this. If you modify this, during the save, the system will display a prompt 'Continue variance on Rollover Flag is modified'.

You can check this box to enable continued variance on rollover. If you check this, then the system will default account variance as current value to the rollover deposit for the next cycle.

If you do not check this, then the account variance will not be carried forward to next rollover cycle.

UDE Values

Variance

Specify the variance profit value alone. The effective rate will be the sum of the TD rate code and the variance that you specify here. This value can be modified at any point of time.

Refer the section 'Specifying Profit Details' in the chapter 'Creating Islamic Account' in this User Manual for further details.

Refer the chapter 'Creating Islamic Account' in this User Manual for further details about the aforesaid buttons..

4.4.8 Specifying TD Payout Details

To define payout parameters for a TD account, click the 'Term Deposit Payout Details' button in the 'Islamic TD Accounts Maintenance' screen. The 'Term Deposit Payout Details' screen is displayed.

The screenshot shows a software window titled "Term Deposit Payout Details". At the top, there are "New" and "Enter Query" buttons. Below this, there are input fields for "Branch", "Account", and "Currency". A horizontal bar contains "Term deposit", "Bankers Cheque / Demand Draft", and "PC". Below this bar, there are input fields for "Branch", "Currency", and "Customer No". To the right, there are radio buttons for "Default From" (selected "Parent Account") and "Account Class", along with an "Account Class" input field. At the bottom left, there is a "Profit" button. At the bottom right, there are "Ok" and "Exit" buttons.

For further details related TD Payout Details, refer 'TD Additional Details' chapter of 'Term Deposits' User Manual.

4.4.8.1 Capturing Payout Profit Details for Child TD

If you have opted for creation of a child TD on maturity of the parent TD, you need to specify Profit details of the child TD. Click 'Profit' button on the 'Term Deposit Payout Details' screen

and invoke the 'Term Deposit Profit' screen. In this screen, the system defaults all the parameters maintained for the parent TD. However, you can modify them.

The screenshot displays the 'Term Deposit Profit' application window. It features a title bar with a diamond icon and window controls. Below the title bar is a section labeled 'Account Details' with two tabs: 'Profit' and 'Deposit'. The 'Profit' tab is active. This section contains several input fields for account information, including 'Calculation Account', 'Calculation Account Description', 'Profit Booking Account', 'Profit Booking Account description', 'Charge Booking Account', and 'Charge Booking Account Description'. There are also date fields for 'Profit Start Date' and 'Charge Start Date', a 'Profit Booking Branch' field, and a 'Charge Booking Branch' field. A checkbox labeled 'Dr Cr Advices' is present. Below these fields is a 'Profit Statement' checkbox. The 'Product Details' section follows, with a 'Product Code' field, a 'UDE Currency' field, an 'ILM Product' checkbox, and an 'ILM Product Type' field. To the right of these fields are four checkboxes: 'Waive Charges', 'Generate UDE Change Advice', 'Open', and 'Continue Variance on Rollover'. Below the 'Product Details' section are two data grids. The first grid has columns for 'Effective Date' and 'Open', with a 'Go' button and navigation arrows. The second grid has columns for 'User Defined Element Id', 'UDE Value', 'Rate Code', and 'Variance', also with a 'Go' button and navigation arrows. At the bottom of the window is a 'Payout Parameters' section, which is currently empty. The window concludes with 'Ok' and 'Exit' buttons.

This screen comprises two tabs viz:

- Profit
- Deposit

4.4.8.2 Profit Tab (Profit Preferences for Child TD)

You need to capture the following details here:

Profit Booking Account

Specify the accounts for booking profits on transactions processed at your bank, from the adjoining option list.

Profit Start Date

The system displays the Maturity date of the parent TD as the profit start date for the child TD. However, you can modify it. Profit for this account will be calculated according to the special conditions that you define subsequently.

Booking Account Branch

The current branch of the customer's account will be defaulted here. However, you can modify profit to a different account belonging to another branch also by specifying Profit Booking Branch from the adjoining option-list. The accounts maintained in the selected Booking Branch will be available in the option-list provided for Booking Account Branch.

Profit Statement

Check this box if you would like to generate a profit statement for the account. The Profit Statement will furnish the values of the SDEs and UDEs and the profit rule that applies on the account.

Cr Advices

Check this box to indicate that the system must generate payment advices when profit liquidation happens on an account. The advices are generated in the existing SWIFT or/and MAIL format. No advices will be generated if you leave this box unchecked.

The preference you have maintained in the Customer Account Class screen will be defaulted here. However, you can choose to change your preference to generate or suppress these Advices.

For further details related preferences for child TD, refer 'TD Additional Details' chapter of 'Term Deposits' User Manual.

4.5 Viewing Islamic TD Account Details

You can view the Islamic TD accounts details maintained in the 'Islamic TD Accounts Maintenance' screen using the 'Islamic TD Accounts Summary' screen. You can invoke this

screen by typing 'IASCUSTD' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The screenshot shows the 'Islamic TD Accounts Summary' application window. It includes a search section with the following fields and controls:

- Case Sensitive:
- Authorization Status:
- Record Status:
- Branch Code:
- Customer Number:
- Stock Catalog Code:
- Term Deposit Account Number:
- Term Deposit Currency:
- Certificate Number:

Below the search fields are buttons for 'Search', 'Advanced Search', 'Refresh', and 'Reset'. A table below shows search results with columns: Authorization Status, Record Status, Branch Code, Term Deposit Account Number, Account Description, and Customer ID. The table currently displays one record. At the bottom right is an 'Exit' button.

In the above screen, you can base your queries on any or all of the following parameters and fetch records:

- Authorization Status
- Branch Code
- Record Status
- Account
- Customer Number
- Term Deposit Currency
- Stock Catalog Code
- Certificate Number

Select any or all of the above parameters for a query and click 'Search' button. The records meeting the selected criteria are displayed.

Note

You can query or modify the account details of the customers whose accounts are permitted to you for the query/modification in the 'Group Code Restriction' screen.

If you are allowed to query customer information, system displays the following details pertaining to the fetched records:

- Authorization Status
- Record Status

- Branch Code
- Account
- Description
- Customer Number
- Currency
- Account Class
- No Debits
- No Credits
- Stop Payments
- Dormant
- Account Open Date
- Alternate Account Number
- Cheque Book
- Passbook
- Account Number
- Account Type
- Frozen

4.6 Input and Authorization Limit Validation for TD

The role level limit set up for a user in 'Role Limits Maintenance' (SMDRLMNE) screen is applicable for transactions on Islamic Term Deposit accounts. If the user has auto authorization rights, while saving the transaction, input limit is validated first. If the input amount is within the input limit then subsequently the authorization limit is validated.

At the time of input/authorization of a deposit transaction, if there is a breach of limit then system displays a configurable override message.

Note

- The role level limit set up done in SMDRLMNE screen is not applicable for branch screens.
 - You can set up a common limit for each channel and for all the deposit transactions done through a channel validation is done against that limit.
 - Limit restrictions will not be validated during deposit amendment.
 - Limit validations are applicable for excel upload.
-

Limit restrictions are not applicable for all type of simulation screens. Limit validation is not be applicable for the following types of deposits:

- Auto Deposit
- Sweep
- Structured Deposit.

Limit validation is applicable for the following types of transactions:

- Term Deposit Opening – Term Deposit amount (Principal amount/Deposit Amount) is considered as the transaction amount.

- Term Deposit Redemption – The transaction amount is inclusive of Term Deposit amount + Interest earned. Interest amount refers to the total interest earned before deducting tax and penalty amount if any.
- Limit control is applicable for partial redemption as well as for full redemption.
- Manual renewal – In case of manual renewal the total renewal amount is validated against the limit. The role level limit control should be applicable for the Term Deposit transactions made through the following fast paths.

The role level limit control is applicable for the Term/Recurring Deposit transactions made through the following screens:

- IADCUSTD - Term Deposit Opening

4.7 IADREDMN - Term Deposit Redemption & Renewal Redeeming TD

The redemption option enables you to redeem a term deposit. Using this option, you can do a premature redemption, either in full or in part and also complete redemption on maturity of the deposit. This screen also allows you to renew the TD. However, renewal of the TD is enabled only if you have specified 'Grace period for Renewal' option for the account.

You can do this, by accessing the TD Redemption screen. You can invoke the 'Term Deposits Redemption Input' screen by typing 'IADREDMN' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Only unclaimed TD accounts in grace days can be renewed. If you try to renew a TD which is not in grace period, the system displays an error message "Only matured TD account can be renewed".

You have to specify the following fields for redeeming the TD.

Reference Number

The system displays the reference number here.

Note

This field will be enabled only for the query mode.

Branch

Specify the branch where the TD resides. The adjoining option list displays all valid branch codes maintained in the system. You can select the appropriate one.

Customer Identification

The customer identification (CIF) of the customer for whom TD needs to be renewed or redeemed is displayed based on the TD account number.

Term Deposit Account Number

Specify the TD Account Number. You can also choose the appropriate one from the option list. The option list displays the deposit type of accounts maintained in the system.

Note

The option list does not display auto deposit type of accounts.

Account Currency

The TD currency is displayed here based on the TD account number.

Account Description

A description of the TD is displayed here based on the TD account number.

Account Balance

The account balance is displayed here based on the TD account number.

Rollover/Redemption

Choose 'Renewal' option to renew the accounts that are within the grace period days. Choose 'Redemption' to redeem the term deposit.

Note

- When a term deposit is moved to unclaimed on maturity date, you have to manually renew or roll over the same term deposit. Once you choose the option, 'Renewal' the 'Term Deposit Account Number' field displays those accounts whose balances are moved to unclaimed GL.
 - The accounting entries for redemption/renewal are passed only on authorization.
-

Rollover

Indicate the rollover tenor for the TD account. You can select one of the following options:

- Account Class Tenor - If 'Recompute Maturity Date on Rollover' is checked at the account class level, then by default, this option is selected. If you select this option, then the following are applicable:
 - The value of 'Default Tenor' at account class is considered as the 'Rollover Tenor' during deposit rollover

- During opening or modification within the term of the deposit, if you change the defaulted value for 'Rollover Tenor' from 'Account Class Tenor' to 'Account Tenor' or 'Independent Tenor', then on save system displays the override message, "Recompute Maturity Date on Rollover restrictions at account class will be ignored".
- On save, the system displays the 'Next Maturity Date'.
- Account Tenor - If 'Recompute Maturity Date on Rollover' is unchecked at the account class level, then by default, this option is selected. If you select this option, then the following are applicable:
 - The value of 'Original Tenor' of the deposit account is considered as the 'Rollover Tenor' during deposit rollover.
 - During opening or modification within the term of the deposit, if you change the defaulted value for 'Rollover Tenor' from 'Account Tenor' to 'Account Class Tenor', then on save system displays the override message, "Recompute Maturity Date on Rollover restrictions at account class will be ignored".
 - On save, system updates the 'Next Maturity Date' with the sum of maturity date and original tenor of the deposit.
- Independent Tenor - Select this option to provide a different tenor, rather than default from account class or account tenor. On selecting this option, you can specify the Rollover Tenor in years, months and days combination. On save, system updates the 'Next Maturity Date' accordingly.

Years

Specify the number of years in the rollover tenor. You can edit this only in the case of Independent tenor.

Months

Specify the number of years in the rollover tenor.

Days

Specify the number of years in the rollover tenor.

Next Maturity Date

On selecting the rollover for the TD account, the system defaults the next maturity date from the previous tenor of the deposit.

Continue Variance on Rollover

The system defaults it based on the flag availability in the TD account level. However, you can modify this flag.

If you check this, then the system will default account variance as current value to the rollover deposit for the next cycle.

If you do not check this, then the account variance will not be carried forward to next rollover cycle.

Redemption

Indicate the following details if you have chosen 'Redemption'.

Redemption Mode

Select the mode of redemption from the following options.

- Full Redemption - In this case, you can redeem the complete deposit balance of the account. On save, the redemption amount will be equal to the account balance. Full redemption will update the status of the deposit amount as closed. On complete

redemption profit along with principal is redeemed. The redemption amount is equal to the total of principle and profit amounts subtracted by penalty and tax amounts.

- Partial Redemption - In this case you have to specify the redemption amount. Ensure that that the redemption amount is less than the account balance. On partial redemption only the principal amount is withdrawn where as the profit amount is liquidated only on liquidation cycle.

Redemption Amount

Specify the redemption amount for the partial redemption. Ensure that that the redemption amount is less than the account balance. On partial redemption only the principal amount is withdrawn where as the profit amount is liquidated only on liquidation cycle.

Note

The system will validate for the following:

- During partial redemption the withdrawal amount should be a multiple of withdrawal unit maintained at the 'Deposits Cluster Maintenance' level, else the system will display the error message as, "Withdrawal amount must be multiples of withdrawal unit."
 - Withdrawal amount should be greater than minimum booking amount maintained at the 'Deposits Cluster Maintenance' level, else the system will display the error message as, "Withdrawal exceeds minimum balance level."
-

Waive Compensation

Check this field to waive any compensation related to the deposit redemption.

Waive Profit

Check this box to waive of a particular profit that has been specified.

Tenor

Specify the following details for TD tenor in case you are renewing the TD.

Days

Specify the renewal tenor in terms of days.

Months

Specify the renewal tenor in terms of months.

Years

Specify the renewal tenor in terms of years.

Redemption By

Select the means of redemption from the following options:

- Savings
- General Ledger
- Bank Check

4.7.1 Bank - Cheque Tab

By default, this tab is displayed when the screen is invoked. You can capture the following details:

Cheque Details

Specify the following cheque details.

Bank Code

Specify the bank code of the Bankers cheque.

Cheque Date

Specify the cheque date for the redemption.

Cheque Currency

Specify the currency in which the cheque is drawn. The adjoining option list displays all valid currency codes maintained in the system. You can select the appropriate one.

Cheque Amount

The amount being liquidated for the TD is displayed in the cheque currency.

Exchange Rate

In case the TD currency is different from the cheque currency; the exchange rate used to convert TD currency into cheque currency is displayed here, based on the rate maintained for the currency pair.

Beneficiary Details

Indicate the following details.

Beneficiary Name

Specify the name of the beneficiary for the redemption.

Passport/IP

Specify passport details for the beneficiary.

Narrative

Give a brief description for the redemption.

Address Line 1 to 3

Specify the address of the beneficiary for the redemption.

4.7.2 Savings Tab

If means of redemption is 'Savings', then click 'Savings' tab.

The screenshot shows the 'Term Deposits Redemption Input' form. It includes fields for Reference No, Branch Code, Customer Id, Currency, Account Number, Account Description, Account Amount, and Action Flag. The Action Flag has radio buttons for Rollover and Redemption. The Redemption section includes a dropdown for Redemption Mode (set to Partial Redemption), a field for Redemption Amount, and checkboxes for Waive Compensation and Waive Profit. The Redemption By section has radio buttons for Savings, General Ledger, and Bankers Cheque. The Rollover Tenor section includes radio buttons for Account Class Tenor, Account Tenor, and Independent Tenor, and fields for Years, Months, and Days. The Next Maturity Date field is also present, along with a checkbox for Continue Variance on Rollover. At the bottom, there are tabs for Bank-Cheque, Savings, and General Ledger. The Savings tab is selected, showing fields for Savings Branch, Savings Account Number, Savings Account Currency, Exchange Rate, Savings Amount, and Narrative. The bottom of the form has fields for Maker, Checker, Date Time, Mod No, Record Status, and Authorization Status, along with an Exit button.

You can capture the following details:

Savings Account Number

Specify the account number into which the TD has to be liquidated. The adjoining option list displays all valid savings accounts maintained in the system. You can choose the appropriate one.

Savings Account Currency

Based on the account number specified, the account currency is displayed here.

Exchange Rate

In case the TD currency is different from the account currency, the exchange rate used to convert TD currency into account currency is displayed here, based on the rate maintained for the currency pair.

Savings Amount

The amount being liquidated for the TD is displayed in the account currency.

Narrative

Give a brief description for the transaction, if required.

4.7.3 General Ledger Tab

If you have indicated the means of redemption as 'General Ledger', then click the 'General Ledger' tab on the 'Term Deposits Redemption Input' screen.

Specify the following details:

General Ledger Number

Specify the GL into which the TD has to be liquidated. The adjoining option list displays all valid GLs maintained in the system. You can choose the appropriate one.

Exchange Rate

In case the TD currency is different from the transaction currency, the exchange rate used to convert TD currency into transaction currency is displayed here, based on the rate maintained for the currency pair.

Transaction Amount

The amount being liquidated for the TD is displayed in the transaction currency.

Transaction Currency

Specify the currency in which the TD should be liquidated. The adjoining option list displays all valid currency codes maintained in the system. You can select the appropriate one.

Narrative

Give a brief description for the transaction, if required.

4.7.4 Authorizing Transaction

For the transaction to be authorized, click 'Authorize' button. The following screen will be displayed:

The screenshot shows the 'Authorize' window with the following data:

| Modification Number | Modification Status | First Authorization Status | Authorization Status | Maker ID | Maker Date S |
|---------------------|---------------------|----------------------------|----------------------|----------|--------------|
| 1 | N | A | Unauthorized | DOCUMEN2 | 2012-11-07 2 |

Remarks section:

Maker Remarks:

First Checker Remarks:

Maker Override Remarks:

Checker Remarks:

| Warning Code | Warning Description |
|--------------|---------------------|
|--------------|---------------------|

| Field Name | Old Value | New Value |
|------------|-----------|-----------|
|------------|-----------|-----------|

Buttons: Accept, Reject, Cancel

Note

The accounting entries for redemption/renewal are passed only on authorization.

4.8 Viewing TD Redemption Details

You can view the details of TDs redemption using the 'Term Deposit Redemption Summary' screen. To invoke this screen, type 'IASREDMN' in the field at the top right corner of the Application tool bar and click the adjoining arrow button.

The screenshot shows the 'Term Deposits Redemption Summary' application window. The window title is 'Term Deposits Redemption Summary'. It features a search bar with options for 'Search', 'Advanced Search', 'Reset', and 'Clear All'. Below the search bar is a 'Case Sensitive' section with various input fields: 'Authorization Status', 'Record Status', 'Reference No', 'Account Number', 'Branch Code', 'Customer Id', 'Action Flag', 'Redemption By', and 'Redemption Amount'. A table below these fields shows a list of records with columns for 'Authorization Status', 'Record Status', 'Reference No', 'Account Number', 'Branch Code', 'Customer Id', and 'Action Flag'. The table currently displays one record. At the bottom right of the window is an 'Exit' button.

You can query on records based on any one or all of the following criteria:

- Authorization Status
- Record Status
- Reference Number
- Account Number
- Branch Code
- Customer Id
- Action Flag
- Redemption By
- Redemption Mode
- Redemption Amount

Click 'Search' button. The system identifies all records satisfying the specified criteria and displays the following details for each one of them:

- Authorization Status
- Record Status
- Reference Number
- Branch Code
- Account Number
- Customer Id
- Action Flag
- Redemption By

4.9 Redeeming TD Partially

On partial redemption of a TD, the system credits the redemption amount to the customer payout account and debits it from the TD account. It recalculates the tenor for the redemption amount i.e. completed tenor from the TD value date till the partial redemption date in months. This indicates the reduced tenor.

It also recalculates the profit for the previous periods including the current period (till partial redemption date) by considering the redemption amount as the TD amount for the reduced tenor. It applies the broken weight during profit recalculation and arrives at a certain amount - say Amount1.

It recalculates the profit for the remaining amount from TD start date till the last liquidation period by considering the remaining amount as TD balance for the original tenor of TD and arrives at another amount – say Amount2.

In case of TD pay-outs, the system captures the profit amount paid to the customer till date – say Amount3.

If the profit for the previous periods has been already paid to the customer, then the customer will be debited with the difference amount between already liquidated amount till the last liquidation date and the newly recalculated profit (for redemption amount and remaining amount). This means, the customer will be debited with $[Amount3 - (Amount1 + Amount2)]$.

The balance amount after partial redemption will be considered as the new TD with the original TD tenor by the system.

5.1 Introduction

Information about the Islamic accounts can be retrieved as a report.

When you seek information in the form of a display, on the basis of certain parameters, you generate a 'report'. Typically, you would 'query' the system to provide your customer with immediate information.

Note

Save the relevant record in the General Ledger Average Balance (GLDVWBAL) screen, before generating reports for the following function IDs:

IARMAVGB
IARMBLPD
IARMURBL
IARMMPDR
IARMAQBL
IARMMQBL

5.2 Mudarabah Monthly Average Balance Report on Month End for Savings

The Mudarabah Monthly Average Balance Report on Month End for Savings provides details of monthly average balance at month end for Mudarabah savings account. You can invoke the screen by typing the code 'IARMAVGB' in the field at the top right corner of the Application tool bar and click on the adjoining arrow button.

The screenshot shows a software window titled "Mudarabah Monthly Average Balance Report on Month End for Savings". The window contains several input fields and dropdown menus for configuring the report. On the left side, there are fields for "Last Day of the Month", "Financial Year", and "Period Code". Below these are "Report Format" (set to "PDF") and "Report Output" (set to "Print"). On the right side, there are "Printer At" (set to "Client") and "Printer" fields. At the bottom right corner, there are "Ok" and "Exit" buttons.

You can specify the following parameters here:

Last Day of the Month

Specify date of the last day of month for which you want to generate the report from the adjoining calendar.

Financial Year

Specify the financial year for which you want to generate the report from the adjoining option list.

Period Code

System defaults the period code of the specified Financial Year.

5.2.1 Contents of the Report

The parameters specified while generating the report are printed at the beginning of the report. Other content displayed in the report is as follows:

Header

The following details are displayed in the header section:

| Field Name | Field Description |
|-------------|---|
| Branch | Indicates Branch Code and Branch Name |
| Branch Date | Indicates Current Date of the Branch |
| User ID | Indicates User ID |
| Date & Time | Indicates the Date and Time when the report was generated |
| Module | Indicates module for which report is generated. |

Body of the Report

The following details are displayed as body of the generated report:

| Field Name | Field Description |
|-----------------------|---|
| Account Class | Indicates account class of the account number |
| Account Number | Indicates account number of the customer |
| Account Description | Indicates account description of the account number |
| Account Opening Date | Indicates account opening date |
| Balance | Indicates balance in the account |
| Last Declaration Rate | Indicates last declaration date |

5.3 Mudarabah Monthly Average Balance Report on Profit Distribution Date for Savings

The Mudarabah Monthly Average Balance Report on Profit Distribution Date for Savings provides details of monthly average balance on profit distribution date for Mudarabah savings.

You can invoke the screen by typing the code 'IARMBLPD' in the field at the top right corner of the Application tool bar and click on the adjoining arrow button.

You can specify the following parameters here:

Financial Year

Specify the financial year for which you want to generate the report from the adjoining option list.

Period Code

System defaults the period code of the specified Financial Year.

Profit Distribution Date

Specify date profit distribution for which you want to generate the report from the adjoining calendar.

5.3.1 Contents of the Report

The parameters specified while generating the report are printed at the beginning of the report. Other content displayed in the report is as follows:

Header

The following details are displayed in the header section:

| Field Name | Field Description |
|-------------|---|
| Branch | Indicates Branch Code and Branch Name |
| Branch Date | Indicates Current Date of the Branch |
| User ID | Indicates User ID |
| Date & Time | Indicates the Date and Time when the report was generated |
| Module | Indicates module for which report is generated. |


Body of the Report

The following details are displayed as body of the generated report:

| Field Name | Field Description |
|--|--|
| Account Class | Indicates account class of the account number |
| Branch | Indicates the branch code |
| Account Number | Indicates account number of the customer |
| Account Description | Indicates account description of the account number |
| Account Opening Date | Indicates account opening date |
| Currency | Indicates currency code of the account |
| Monthly Average Balance (Account Currency) | Indicates monthly average balance of the account in account currency |
| Monthly Average Balance (Local Currency) | Indicates monthly average balance of the account in local currency |
| Last Declared Rate | Indicates last rate declared |

5.4 Mudarabah Monthly Minimum Balance Report on Month End for Savings

The Mudarabah Monthly Minimum Balance Report on Month End for Savings provides details of monthly minimum balance at month end for Mudarabah savings account. You can invoke the screen by typing the code 'IARMURBL' in the field at the top right corner of the Application tool bar and click on the adjoining arrow button.



The screenshot shows a software window titled "Mudarabah Monthly Min Bal Report on Month End for Savings". The window contains several input fields and dropdown menus for configuring the report. On the left side, there are three text input fields labeled "Last Day of the Month", "Financial Year", and "Period Code". Below these are two dropdown menus: "Report Format" set to "PDF" and "Report Output" set to "Print". On the right side, there are two more dropdown menus: "Printer At" set to "Client" and "Printer" which is currently empty. At the bottom right corner of the window, there are two buttons labeled "Ok" and "Exit".

You can specify the following parameters here:

Last Day of the Month

Specify date of the last day of month for which you want to generate the report from the adjoining calendar.

Financial Year

Specify the financial year for which you want to generate the report from the adjoining option list.

Period Code

System defaults the period code of the specified Financial Year.

5.4.1 Contents of the Report

The parameters specified while generating the report are printed at the beginning of the report. Other content displayed in the report is as follows:

Header

The following details are displayed in the header section:

| Field Name | Field Description |
|-------------|---|
| Branch | Indicates Branch Code and Branch Name |
| Branch Date | Indicates Current Date of the Branch |
| User ID | Indicates User ID |
| Date & Time | Indicates the Date and Time when the report was generated |
| Module | Indicates module for which report is generated. |


Body of the Report

The following details are displayed as body of the generated report:

| Field Name | Field Description |
|--|--|
| Account Class | Indicates account class of the account number |
| Branch | Indicates the branch code |
| Account Number | Indicates account number of the customer |
| Account Description | Indicates account description of the account number |
| Account Opening Date | Indicates account opening date |
| Currency | Indicates currency code of the account |
| Monthly Average Balance (Account Currency) | Indicates monthly average balance of the account in account currency |
| Monthly Average Balance (Local Currency) | Indicates monthly average balance of the account in local currency |
| Monthly Minimum Balance (Account Currency) | Indicates monthly minimum balance of the account in account currency |
| Monthly Minimum Balance (Local Currency) | Indicates monthly minimum balance of the account in local currency |
| No Of Dr Transactions | Indicates number of debit transactions in the account |
| Last Declaration Rate | Indicates last declaration date |

5.5 Mudarabah Monthly Minimum Balance Report on Profit Distribution Date for Savings

The Mudarabah Monthly Minimum Balance Report on Profit Distribution Date for Savings provides details of monthly minimum balance on profit distribution date for Mudarabah savings account. You can invoke the screen by typing the code 'IARMMPDR' in the field at the top right corner of the Application tool bar and click on the adjoining arrow button.



You can specify the following parameters here:

Profit Distribution Date

Specify valid profit distribution date for which you want to generate the report from the adjoining calendar.

Financial Year

Specify the financial year for which you want to generate the report from the adjoining option list.

Period Code

System defaults the period code of the specified Financial Year.

5.5.1 Contents of the Report

The parameters specified while generating the report are printed at the beginning of the report. Other content displayed in the report is as follows:

Header

The following details are displayed in the header section:

| Field Name | Field Description |
|-------------|---|
| Branch | Indicates Branch Code and Branch Name |
| Branch Date | Indicates Current Date of the Branch |
| User ID | Indicates User ID |
| Date & Time | Indicates the Date and Time when the report was generated |

| | |
|--------|---|
| Module | Indicates module for which report is generated. |
|--------|---|

Body of the Report

The following details are displayed as body of the generated report:

| Field Name | Field Description |
|--|--|
| Account Class | Indicates account class of the account number |
| Branch | Indicates the branch code |
| Account Number | Indicates account number of the customer |
| Account Description | Indicates account description of the account number |
| Account Opening Date | Indicates account opening date |
| Currency | Indicates currency code of the account |
| Monthly Average Balance (Account Currency) | Indicates monthly average balance of the account in account currency |
| Monthly Average Balance (Local Currency) | Indicates monthly average balance of the account in local currency |
| Monthly Minimum Balance (Account Currency) | Indicates monthly minimum balance of the account in account currency |
| Monthly Minimum Balance (Local Currency) | Indicates monthly minimum balance of the account in local currency |
| No Of Dr Transactions | Indicates number of debit transactions in the account |
| Last Declaration Rate | Indicates last declaration date |

5.6 Mudarabah Quarterly Average Balance Report for Savings

The Mudarabah Quarterly Average Balance Report for Savings provides details of quarterly average balance of Mudarabah savings accounts. You can invoke the screen by typing

'IARMAQBL' in the field at the top right corner of the Application tool bar and click on the adjoining arrow button.

You can specify the following parameters here:

Last Day of the Quarter

Specify date of the last day of quarter for which you want to generate the report from the adjoining calendar.

Financial Cycle

Specify the financial cycle for which you want to generate the report from the adjoining option list.

Period Code

System defaults the period code of the specified Financial Cycle.

5.6.1 Contents of the Report

The parameters specified while generating the report are printed at the beginning of the report. Other content displayed in the report is as follows:

Header

The following details are displayed in the header section:

| Field Name | Field Description |
|-------------|---|
| Branch | Indicates Branch Code and Branch Name |
| Branch Date | Indicates Current Date of the Branch |
| User ID | Indicates User ID |
| Date & Time | Indicates the Date and Time when the report was generated |
| Module | Indicates module for which report is generated. |


Body of the Report

The following details are displayed as body of the generated report:

| Field Name | Field Description |
|--|--|
| Account Class | Indicates account class of the account number |
| Branch | Indicates the branch code |
| Account Number | Indicates account number of the customer |
| Account Description | Indicates account description of the account number |
| Account Opening Date | Indicates account opening date |
| Currency | Indicates currency code of the account |
| Monthly Average Balance (Account Currency) | Indicates monthly average balance of the account in account currency |
| Monthly Average Balance (Local Currency) | Indicates monthly average balance of the account in local currency |
| Category | Indicates category |

5.7 Mudarabah Quarterly Minimum Balance Report for Savings

The Mudarabah Quarterly Minimum Balance Report for Savings provides details of quarterly minimum balance for Mudarabah savings account. You can invoke the screen by typing the code 'IARMMQBL' in the field at the top right corner of the Application tool bar and click on the adjoining arrow button.



The screenshot shows a dialog box titled "Mudarabah Quarterly Minimum Balance Report for Savings". It contains the following fields and controls:

- Date Selection**: A section header.
- Report Date - Last Day of Quarter**: A text input field.
- Report Format**: A dropdown menu with "PDF" selected.
- Report Output**: A dropdown menu with "Print" selected.
- Printer At**: A dropdown menu with "Client" selected.
- Printer**: A text input field.
- Buttons**: "Ok" and "Exit" buttons at the bottom right.

You can specify the following parameters here:

Report Date - Last day of the Quarter

Specify date of last day of the quarter for which you want to generate the report from the adjoining calendar.

5.7.1 Contents of the Report

The parameters specified while generating the report are printed at the beginning of the report. Other content displayed in the report is as follows:

Header

The following details are displayed in the header section:

| Field Name | Field Description |
|-------------|---|
| Branch | Indicates Branch Code and Branch Name |
| Branch Date | Indicates Current Date of the Branch |
| User ID | Indicates User ID |
| Date & Time | Indicates the Date and Time when the report was generated |
| Module | Indicates module for which report is generated. |

Body of the Report

The following details are displayed as body of the generated report:

| Field Name | Field Description |
|--|--|
| Branch Code | Indicates Branch Code |
| Branch Name | Indicates Branch Name |
| Account Number | Indicates Customer Account number |
| Title of the Account | Indicates Account Title |
| Account Class | Indicates Account Class of the account |
| Account Opening Date | Indicates Date of opening account |
| Account Currency | Indicates account Currency code |
| Monthly Minimum Balance Month 1 | Indicates monthly minimum balance for 1 st month |
| Number of Debit Transaction During Month 1 | Indicates number of debit transactions for 1 st month |
| Monthly Minimum Balance Month 2 | Indicates monthly minimum balance for 2 nd month |
| Number of Debit Transaction During Month 2 | Indicates number of debit transactions for 2 nd month |
| Monthly Minimum Balance Month 3 | Indicates monthly minimum balance for 3 rd month |
| Number of Debit Transaction During Month 3 | Indicates number of debit transactions for 3 rd month |

6. Annexure A - IP Rule Set-up

6.1 Introduction

This Annexure lists the Profit and Charge (IP) rules that need to be maintained for the Islamic TD module of Oracle FLEXCUBE specifically for partial redemption of TD.

6.2 IP Rule Maintenance

The components required to calculate profit (the principal, period, and rate) are broadly referred to as 'Data Elements'. Data elements are of two types:

- System Data Elements (SDEs)
- User Data Elements (UDEs)

In addition to specifying how the SDEs and UDEs are connected through the formulae, you also define certain other attributes for a rule using the 'Profit and Charges Rule Maintenance' screen. You can invoke this screen by typing 'IPDRLMNT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Profit and Charges Rule Maintenance' screen. It includes the following components:

- Form Fields:** Rule Id *, Rule Description *, Primary Element.
- Apply Interest:** On Account Opening Month, On Account Closure Month.
- ILM Parameters:** Integrated LM, Integrated LM Type (dropdown).
- System Elements Table:**

| System Elements * |
|-------------------|
| [Field] |
- User Elements Table:**

| User Elements * | Type | Get Latest |
|-----------------|--------|---------------|
| [Field] | Amount | Use Effective |
- Bottom Bar:** Formulas | Fields | Formula Rate. Input By: [Field], Date Time. Authorized By: [Field], Date Time. Modification Number: [Field]. Authorized, Open.

You need to specify the following details:

On Account Opening Month

Check this box.

On Account Closure Month

Check this box.

SDE

Maintain the following SDEs:

- DAYS
- YEAR
- DEPOSIT_AMOUNT

The SDE 'DEPOSIT_AMOUNT' holds the value of the TD account minus the redemption amount.

UDE

Maintain the following UDE:

- MUDARABAH_RATE

Type

Select the option 'Rate' from the adjoining drop-down list.

Get Latest

Select the option 'Use Effective' from the adjoining drop-down list.

Click 'Formulas' button and invoke the 'Formulas' screen.

The screenshot displays the 'Formulas' window in Oracle. The interface includes several sections for configuring a formula:

- Formula Number:** A text field for entering the formula identifier.
- Debit/Credit:** A dropdown menu currently set to 'Debit'.
- Accruals Required:** A checkbox that is currently unchecked.
- Tax Category:** A text field with a search icon.
- Tax Description:** A text field.
- Calculation Parameters:**
 - Basis Percent:** A text field.
 - Local Currency Basis:** A checkbox that is currently unchecked.
- Booking:**
 - Book Flag:** A dropdown menu set to 'Booked'.
 - Days in a Month:** A dropdown menu set to 'Actuals'.
 - Interest Method Default From Currency Definition:** A checkbox that is currently unchecked.
 - Book Tax To Expense Account:** A checkbox that is currently unchecked.
 - Tax Payable Currency Flag:** A dropdown menu.
- Basis Amount:**
 - Option:** A dropdown menu.
 - Method:** A dropdown menu.
 - Decimals:** A text field.
 - Units:** A text field.
- Tax Amount:**
 - Option:** A dropdown menu.
 - Method:** A dropdown menu.
 - Decimals:** A text field.
 - Units:** A text field.
- Periodicity:** A dropdown menu set to 'Daily'.
- Days in a Year:** A dropdown menu set to 'Actuals'.
- Rounding Required:** A checkbox that is currently unchecked.

At the bottom of the window, there is a 'Formula Wizard' button.

You need to maintain one booked formulae.

Formula 1

Specify the following details:

Book Flag

Select 'Booked' from the adjoining drop-down list.

Debit/Credit

Select 'Credit' from the adjoining drop-down list.

Days in a Month

Select '30 Days' from the adjoining drop-down list.

Days in a Year

Select '360' from the adjoining drop-down list.


Accrual Required

Check this box.

Rounding Required

Check this box.

Click 'Formula Wizard' button and invoke the 'Formula Wizard' screen.



Specify the following expressions:

| Case | Result |
|--------------------|--|
| DEPOSIT_AMOUNT > 0 | DEPOSIT_AMOUNT * (MUDARABAH_RATE/100) * (DAYS/YEAR) |

For details about the screen, refer the chapter 'Maintaining Interest Rules' in the Interest and Charges User Manual.

6.3 UDE Value Maintenance

You can maintain UDE values for the rules using the 'User Data Element Maintenance' screen. You can invoke the 'Interest & Charges User Data Element Maintenance' screen by

typing 'IPDUDVAL' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

For details about the screen, refer the chapter 'Giving UDE Values for Condition' in the Interest and Charges User Manual.

In this screen, you need to maintain the following UDEs for the different IP products. Assume that you have maintained the following IP products:

- TD with Capitalization
- Normal TD with Simple Profit
- Recurring deposit Scheme

6.3.1 TD with Capitalization

You need to maintain values for the following UDEs under this product:

- TD_1
- TD_2
- TD_3
- TD_PNL
- TAX_RATE

6.3.2 Normal TD with Simple Profit

You need to maintain values for the following UDEs under this product:

- TD_1

- TD_2
- TD_3
- TD_PNL

6.3.3 Recurring Deposit Scheme

You need to maintain values for the following UDEs under this product:

- TD_1
- OVERDUE_PENALTY
- TAX_RATE

For the aforesaid rate code, you need to maintain rates and effective dates in the 'Interest and Charges Rate Input' screen. You can invoke the 'Interest and Charges Rate Input' screen by typing 'IPDRATES' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Interest & Charges Rate Input' application window. The window title is 'Interest & Charges Rate Input'. The interface includes a menu bar with 'New' and 'Enter Query' options. The main area contains several input fields: 'Rate', 'Branch Code *', 'Rate Code *', and 'Currency Code *'. Below these fields is a 'Rates' table with columns 'Effective Date *', 'Rate', and 'Open'. The 'Fields' section at the bottom includes 'Input By Date Time', 'Authorized By Date Time', 'Modification Number', and checkboxes for 'Authorized' and 'Open'.

These rates are picked up by the TD module while processing profit applicable on a TD account.

Refer the chapter 'Floating Rate Codes for IP Module' for details about rate maintenance.

7. Function ID Glossary

A

ADPRMNT 4-6

E

EIDMANPE 2-106

I

IADACCLS 2-2

IADCUSAC 2-35

IADCUSTD 4-8

IADREDMN 4-30

IARMAQBL 5-8

IARMAVGB 5-1

IARMBLPD 5-2

IARMMPDR 5-6

IARMMQBL 5-9

IARMURBL 5-4

IASCUSTD 4-28

IASREDMN 4-36

ICDPRABT 3-8

ICDPRCBT 3-4

ICDPRUPD 3-6

ICDRATES 1-5

ICDWTMNT 3-1

ICDZAKBA 3-13

IPDUDVAL 1-4

S

STDREXBT 2-34