# Oracle® Banking Enterprise Default Management

Integration Guide Release 2.11.0.0.0 **F36758-01** 

December 2020



Oracle Banking Enterprise Default Management Integration Guide, Release 2.11.0.0.0

F36758-01

Copyright @ 2017, 2020, Oracle and/or its affiliates.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Inside are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Epyc, and the AMD logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs (including any operating system, integrated software, any programs embedded, installed or activated on delivered hardware, and modifications of such programs) and Oracle computer documentation or other Oracle data delivered to or accessed by U.S. Government end users are "commercial computer software" or "commercial computer software documentation" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, reproduction, duplication, release, display, disclosure, modification, preparation of derivative works, and/or adaptation of i) Oracle programs (including any operating system, integrated software, any programs embedded, installed or activated on delivered hardware, and modifications of such programs), ii) Oracle computer documentation and/or iii) other Oracle data, is subject to the rights and limitations specified in the license contained in the applicable contract. The terms governing the U.S. Government's use of Oracle cloud services are defined by the applicable contract for such services. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate failsafe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

## **Contents**

Preface	9
Audience	9
Documentation Accessibility	9
Organization of the Guide	9
Related Documents	10
Conventions	10
1 Introduction	12
2 Installing the Host Media Pack	14
2.1 Prerequisites	14
2.2 Installing the OBEDM Host Media Pack	14
2.3 Configuring Weblogic Domain For Host	34
3 Installing the Presentation Media Pack	40
3.1 Prerequisites	40
3.2 Installing the Presentation Media Pack	40
3.3 Configuring Weblogic Domain for Presentation Server	51
3.4 Verifying the Presentation Server Deployment	55
4 External Interface Configuration	58
4.1 Oracle Identity Manager (OIM)	58
5 Installing Third-Party Software	60
5.1 Installing Oracle Java Development Kit (JDK)	60
6 User Creation	62
6.1 User Creation with OID	62
6.2 User Creation with Local Security (in database)	72
7 Threadpool Configuration	78

7.1 Manage Requisite Files in lib	78
7.2 Recommendations for Threadpool Memory Configuration	80
7.3 Start Threadpoolworker	80
7.4 Verification	80
7.5 Submit the Batch	83
7.6 Stop Threadpoolworker	83
7.7 Command-Line Options	84

## **List of Tables**

Table 2–1 Installer: Initial Details in config.properties	17
Table 2–2 Installer: Host Configuration in config.properties	18
Table 2–3 Installer: DB Configuration in config.properties	19
Table 2–4 Installer: Batch Configuration in config.properties	19
Table 2–5 Installer: Threadpool Configuration in config.properties	20
Table 2–6 Installer: Initial Details	24
Table 2–7 Installer: Host Configuration	26
Table 2–8 Installer: Host DB Configuration	27
Table 2–9 Installer: Batch Configuration	28
Table 2–10 Installer: Threadpool Configuration in config.properties	29
Table 2–11 Configuring Weblogic Domain for Host	36
Table 3–1 Installer: Initial Details in config.properties	42
Table 3–2 Installer: Host Configuration in config.properties	43
Table 3–3 Installer: UI Configuration in config.propertiesties	44
Table 3–4 Installer: DB Configuration in config.properties	45
Table 3–5 Installer: Initial Details	48
Table 3–6 Installer: UI Configuration	49
Table 3–7 Configuring Weblogic Domain for Presentation	52
Table 3–8 Verifying the Presentation Server Deployment	56

## **List of Figures**

Figure 2–1 Hibernate tmp folder	15
Figure 2–2 OBEDM_V[Build_Number].zip uncompressed	16
Figure 2–3 Installer: config.properties file	21
Figure 2–4 Weblogic Admin Console	22
Figure 2–5 Summary of servers	22
Figure 2–6 Force shutdown	22
Figure 2–7 Verify Server State	23
Figure 2–8 Installer: Initial Details	24
Figure 2–9 Installer: Host Configuration	25
Figure 2–10 Installer: Host DB Configuration	26
Figure 2–11 Installer: Batch Configuration	28
Figure 2–12 Installer: Threadpool Configuration	29
Figure 2–13 Installer: Confirm Installations Details	30
Figure 2–14 Installer: Confirm Installations Details	30
Figure 2–15 Data Source Connection Pool	31
Figure 2–16 Add XML Registry	31
Figure 2–17 Settings for XML Registry	32
Figure 2–18 Deploy XML Registry	33
Figure 2–19 Host Domain Security	33
Figure 2–20 Summary of servers	34
Figure 2–21 Force shutdown	34
Figure 2–22 Verify Server State	35
Figure 2–23 Weblogic Admin Console	35
Figure 2–24 Domain Configuration: Confirm	37

Figure 3–1 OBEDM_V[Build_Number].zip uncompressed	41
Figure 3–2 Installer: config.properties file	46
Figure 3–3 Weblogic Admin Console	47
Figure 3–4 Installer: Initial Details	48
Figure 3–5 Installer: UI configuration	49
Figure 3–6 Installer: Confirm Installation Details	50
Figure 3–7 Installer : Installing	50
Figure 3–8 XML Registry	51
Figure 3–9 Weblogic Admin Console	52
Figure 3–10 Domain Configuration: Confirm	54
Figure 3–11 Domain Configuration: Proceeding with the Process	54
Figure 6–1 Opening ODSM	62
Figure 6–2 Log in to OID	63
Figure 6–3 Navigating to Data Browser Tab	63
Figure 6–4 Creating New Entry	64
Figure 6–5 Adding Object Classes: Top	65
Figure 6–6 Adding Object Classes: Person	65
Figure 6–7 Adding Object Classes: Oracle User	66
Figure 6–8 Selecting Distinguished Name	66
Figure 6–9 Selecting Entry Properties	67
Figure 6–10 Selecting Mandatory Properties	67
Figure 6–11 Status Message	68
Figure 6–12 Selecting the User	68
Figure 6–13 Attributes Tab	69
Figure 6–14 Adding User Password	69
Figure 6–15 Setting User Password	70

Figure 6–16 Confirm Message	70
Figure 6–17 Adding to Administrator Group	71
Figure 6–18 Attributes Tab	71
Figure 6–19 Confirmation message	72
Figure 6–20 Define Application Role page	73
Figure 6–21 Define Enterprise Role page	74
Figure 6–22 Manage User Creation page - Personal and Profile section	75
Figure 6–23 Manage User Creation page - Others section	75
Figure 6–24 Pass Policy Management page	76
Figure 7–1 Command to Create wlfullclient.jar	78
Figure 7–2 Standalone lib	79
Figure 7–3 ThreadPool Worker Log	80
Figure 7–4 Executing OBE Initialisation Block	81
Figure 7–5 Verify Threadpool Worker: Check Connection	82
Figure 7–6 Submit the Batch	83

### **Preface**

This document will help you to install Oracle Banking Enterprise Collections and Oracle Banking Enterprise Recovery as an integrated module of Oracle Banking Platform. This document assumes that Oracle Banking Platform Presentation and Host environment are pre-installed.

This preface contains the following topics:

- Audience
- Documentation Accessibility
- Organization of the Guide
- Related Documents
- Conventions

#### **Audience**

This document is intended for the following audience:

- IT Deployment Team
- Consulting Staff
- Administrators

### **Documentation Accessibility**

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at <a href="http://www.oracle.com/us/corporate/accessibility/index.html">http://www.oracle.com/us/corporate/accessibility/index.html</a>.

Access to Oracle Support

Oracle customers have access to electronic support through My Oracle Support. For information, visit http://www.oracle.com/us/corporate/accessibility/support/index.html#info or visit http://www.oracle.com/us/corporate/accessibility/support/index.html#trs if you are hearing impaired.

### **Organization of the Guide**

The information in this document is organized into the following chapters and appendices:

Chapter 1 Introduction

This chapter describes the Collections integration.

Chapter 2 Installing the Host Media Pack

This chapter describes the steps involved in installing the host media pack.

Chapter 3 Installing the Presentation Media Pack

This chapter describes the steps involved in installing the presentation media pack.

Chapter 4 External Interface Configuration

This chapter describes the steps involved in Oracle Identity Manager (OIM) Adapter configuration.

#### Chapter 5 Installing Third-Party Software

This chapter describes the required third-party software.

#### Chapter 6 User Creation

This chapter describes the user creation with OID and with local security using database.

#### Chapter 7 Threadpool Configuration

This chapter provides information about threadpool configuration.

#### **Related Documents**

For more information, see the following documentation:

- For information on the configurations that are to be performed on day zero, see the Oracle Banking Enterprise Default Management Day Zero Setup Guide.
- For a brief description about user provisioning in Collections, see the Oracle Banking Enterprise Default Management User Provisioning Guide.

### **Conventions**

The following text conventions are used in this document:

Convention	Meaning
boldface	Boldface type indicates graphical user interface elements associated with an action, or terms defined in text or the glossary.
italic	Italic type indicates book titles, emphasis, or placeholder variables for which you supply particular values.
monospace	Monospace type indicates commands within a paragraph, URLs, code in examples, text that appears on the screen, or text that you enter.



## 1 Introduction

This guide helps you to install Oracle Banking Enterprise Default Management for a seamless integration with Oracle Banking Platform.



## 2 Installing the Host Media Pack

You must follow the steps mentioned below to install the Host Media Pack:

- 1. Install the Host Media Pack 2.11.0.0.0
- 2. Update the environment.
- 3. Configure the WebLogic domain.

### 2.1 Prerequisites

Before you install the Oracle Banking Enterprise Default Management 2.11.0.0.0 Host Media Pack, you must have the following installed on the machine:

- OBP 2.11.0.0.0 Host Media Pack.
- OBP 2.11.0.0.0 Presentation Media Pack.
- Windows Secure Copy (WINSCP) to copy deliverables from Windows to Linux machine.
- Oracle Java Development Kit (JDK) 1.8 Update 231 (For more information on how to install Oracle JDK, see Chapter 5 Installing Third-Party Software.)
- Manager, a PC X server that runs on the Windows platforms and helps launching X applications UI on a Windows desktop.
- OBEDM database must be installed. For more information on installing or configuring database, see the Oracle Banking Enterprise Default Management DBA Guide.
- Download the hibernate-release-4.1.0. Final.zip file from:

http://sourceforge.net/projects/hibernate/files/hibernate4/

It is very important that you download the exact version, as the product has only been certified with this exact release.

## 2.2 Installing the OBEDM Host Media Pack

The OBEDM 2.11.0.0.0 installation package is used for installing both the OBEDM Host and Presentation Media Packs. You can download the installation package from the following location:

https://edelivery.oracle.com/

To install the OBEDM Host Media Pack:


- 1. Log in to the Host Server.
- 2. Create a temporary directory (for example, TEMPDIR) on the Host Server using the following command:

mkdir TEMPDIR

3. Copy the OBEDM 2.11.0.0.0 installation package, OBEDM V[Build Number].zip, which you have downloaded from the edelivery to Host Server by using WINSCP to created TEMPDIR folder.

- 4. Create a Hibernate\_tmp directory and follow the below steps.
  - a. Extract downloaded hibernate-release-4.1.0. Final.zip package in temp directory.
  - b. Copy below jars from extracted hibernate-release-4.1.0/lib/required folder to created hibernate\_ tmp path
    - hibernate-commons-annotations-4.0.1.Final.jar
    - hibernate-core-4.1.0.Final.jar
    - hibernate-jpa-2.0-api-1.0.1.Final.jar
    - jboss-transaction-api\_1.1\_spec-1.0.0.Final.jar
    - dom4j-1.6.1.jar
  - c. Copy hibernate-ehcache-4.1.0.Final.jar from extracted hibernate-release-4.1.0/ lib/optional/ehcache folder to created hibernate\_tmp path.

Figure 2-1 Hibernate tmp folder



5. Uncompress the OBEDM\_V[Build\_Number].zip file using the following command:

```
cd <PATH>/TEMPDIR
unzip OBEDM V[Build Number].zip
```


Where, <PATH> is the path where the TEMPDIR folder is located.

The contents of the zip file are extracted in the TEMPDIR folder. The following files / folders are extracted:

- config.properties
- ouaf.properties
- data
- Install.sh
- Install\_Silent.sh

- collectioninstaller.jar
- collectionupgradeinstaller.jar

Figure 2-2 OBEDM\_V[Build\_Number].zip uncompressed



- 6. Collection installer operates in two modes, go with either mode.
  - a. Silent mode:
    - i. Update config.properties in the TEMPDIR directory
    - ii. Set IS\_STANDALONE = Y
    - iii. Update below sections in config.properties as shown in Figure 2–3:
      - INSTALLER DETAILS
        - IS\_DEV\_ENV=false
        - IS\_UI\_ENABLED=N
      - INITIAL DETAILS
        - HOST\_CONFIG=Y
        - UI\_CONFIG=N
        - BATCH\_CONFIG=Y
        - CUSTOM\_SUPPORT=N
        - THREADPOOL\_CONFIG=N
        - DOMAINNAME=HOST+BATCH
      - HOST CONFIGURATION
      - HOST DB CONFIGURATION
      - BATCH CONFIGURATION
      - THREADPOOL CONFIGURATION

In config.properties: Initial Details section contains the following fields

Table 2–1 Installer: Initial Details in config.properties

Field	Description
Operating System (OPERATING_ SYSTEM)	Used to indicate the operating system on which you want to install the OBEDM Host Media Pack. The options are:
	■ Linux
	■ Windows
	You can only integrate OBEDM with OBP on the Linux environment.
Installation Directory (INSTALL_DIR)	Used to specify the directory where you want to install the OBEDM Host Media Pack. It should be same as the installation directory where OBP Host Media pack is installed.  By default,/scratch/app/product/fmw/obpinstall/obp is specified in this field. You can change the path and directory name, if required.
Generate Host Configuration (HOST_CONFIG)	Used to deploy the OBEDM Host Media Pack components, if HOST_CONFIG is set to Y.
Generate UI Configuration (UI_CONFIG)	Used to deploy the OBEDM Presentation Media Pack components, if UI_CONFIG is set to Y.
Generate Batch Configuration	Used to deploy the batch components used for configuring the batch server, if BATCH_CONFIG option is set Y.
(BATCH_ CONFIG)	If you want to deploy the batch components, you must always set the HOST_CONFIG and BATCH_CONFIG value to Y.
Generate Thread Pool Configuration (THREADPOOL_ CONFIG)	Used to deploy the threadpool components used for configuring the threadpool, if this option is checked.
	If you want to deploy the threadpool components, you must always set the HOST_CONFIG, BATCH_CONFIG and THREADPOOL_CONFIG value to Y.
Customization Support Required (CUSTOM_ SUPPORT)	Used to enable the customization support, if CUSTOM_ SUPPORT is set to Y.
	Used to specify domain name. The options are:
Domain name	■ UI
(DOMAINNAME)	■ HOST
,	■ HOST+BATCH  if BATCH_CONFIG option is set to Y then choose HOST+BATCH.

In config.properties: **Host Configuration** section contains the following fields

Table 2–2 Installer: Host Configuration in config.properties

Field	Description
Host IP address (DB_IP_ADDRESS)	Used to specify the host IP address. For example, 10.180.6.11.
Host port (DB_PORT)	Used to specify the Host server WebLogic managed server port. For example, 8001.
Host Logs Directory (HOST_LOG_DIR)	Used to indicate the directory where the logs must be created on the host server. By default, /scratch/app/product/fmw/obpinstall/obp/fclogs/logs is specified in this field. You can change the path and directory name, if required.
Java Home Path (JAVA_HOME)	Used to indicate the directory where Oracle JDK is installed. By default, /scratch/app/product/jdk1.8.0_231 is specified in this field. You can change the path and directory name, if required.
Hibernate Path (HIBERNATE_ JAR_DIR)	Used to indicate the directory where Hibernate jars downloaded and copied jars from /lib/required/ from extracted hibernate-release-4.1.0.Final.zip package by default, /scratch/app/product/hibernate is specified in this field. You can change the path and directory name, if required. Installer will copy the jars from this directory to Third party directory.
Host weblogic user name (HOST_WEBLOGIC_PASSWORD)	Used to specify the host weblogic username.
Host weblogic password (HOST_ WEBLOGIC_ PASSWORD)	Used to specify the host weblogic password.
Host Admin server port (HOST_ADMINSERVERPORT)	Used to specify the Host server WebLogic admin server port. For example, 7001.

In config.properties: **Host DB Configuration** section contains the following fields:

Table 2-3 Installer: DB Configuration in config.properties

Field	Description
Database IP address (DB_IP_ADDRESS)	Used to specify the database IP address. For example, 10.180.7.77.
Database port (DB_PORT)	Used to specify the database port. For example, 1521.
Database System ID (DB_SID)	Used to specify the database SID. For example, ORA125.
Database user name (DB_USERNAME)	Used to specify the database user name.
Database user password (DB_PASSWORD)	Used to specify the database password.
Host Datasource name (HOST_ DATASOURCE)	Used to specify the host NonXA data source name. For example, jdbc/FCBDataSource_NonXA.

In config.properties: **Batch Configuration** section contains the following fields:

Table 2–4 Installer: Batch Configuration in config.properties

Field	Description
Thread pool name (THREADPOO L_NAME)	Used to specify the name of the thread pool. For example, MT.
Number of threads (NUMBER_OF_ THREADS)	Used to specify the number of the threads that the thread pool can support. For example, 10.
Batch user ID (BATCH_ USER)	Used to specify the batch user ID. For example, SYSUSER.
Batch log directory (BATCH_LOG_ DIR)	Used to specify the batch log directory. For example, /scratch/app/product/fmw/obpinstall/obp/fclogs/logs.

In config.properties: Threadpool Configuration section contains the following fields:

Table 2–5 Installer: Threadpool Configuration in config.properties

Field	Description
Weblogic Server Home (WEBLOGIC_ SERVER_ HOME)	Used to specify the weblogic server home path. For example, /scratch/app/product/fmw/wlserver.
RMI Port (RMI_PORT)	Used to specify the rmi port. For example, 2120.
Host Domain Path (HOST_DOMAIN_ PATH)	Used to specify the Host Domain Path. For example, /scratch/app/product/fmw/user_projects/domains/host_domain.
Cluster Name (CLUSTER_NAME)	Used to specify the Threadpool cluster name. For example, Cluster1
Cluster IP Address (CLUSTER_ MULTICAST_ LISTNER_IP_ ADDRESS)	Used to specify Threadpool cluster IP Address. For Example, 232.0.01
Cluster Port (CLUSTER_ MULTICAST_ LISTNER_PORT)	Used to specify Threadpool Cluster Port. For Example, 6660
Target JMS Module (TARGETTYPE)	Used to specify target JMS Module:  Server  Cluster
Target JMS Module name (TARGETJMSSERVER)	If TARGETTYPE set to 1 i.e Server then provide the name of the managed server. Eg(obphost_server1).  If TARGETTYPE set to 2 i.e Cluster then provide the name of the cluster. Eg(obphost_cluster1).

Figure 2-3 Installer: config.properties file

```
#INSTALLER DETAILS
IS_DEV_ENV=false
OBP_HOST_LIB=ob.host.app/ob.app.host.coll/APP-INF/lib
OBP THIRDPARTY LIB=ob.host.app/ob.app.host.tp/APP-INF/lib
IS UI ENABLED-N
IS STANDALONE-Y
#INITIAL DETAILS
OPERATING_SYSTEM -Linux
INSTALL_DIR=/scratch/app/product/fmm/obpinstall/obp
HOST CONFIG=Y
UI CONFIG-N
BATCH_CONFIG=Y
CUSTOM_SUPPORT-N
THREADPOOL_CONFIG=Y
DOMAINNAME-HOST+BATCH
#UI CONFIGURATION
UI_LOG_DIR=/scratch/app/product/fmw/obpinstall/obp/fclogs/logs
UI_IP_ADDRESS=
UI_PORT=8001
UI_WEBLOGIC_USERNAME=weblogic
UI WEBLOGIC PASSWORD
UI_DATASOURCE=jdbc/FCBDataSource_NonXA
UI_ADMINSERVERPORT=7001
#HOST CONFIGURATION
HOST IP ADDRESS-
HOST_PORT=8001
HOST_LOG_DIR=/scratch/app/product/fmw/obpinstall/obp/fclogs/logs
JAVA_HOME=/scratch/app/product/jdk1.8.0 231
HIBERNATE JAR DIR=/scratch/ofssobp/Hibernate_tmp
HOST_WEBLOGIC_USERNAME=weblogic
HOST_WEBLOGIC_PASSWORD=
HOST_DATASOURCE=jdbc/FCBDataSource_NonXA
HOST_ADMINSERVERPORT=7001
#DB CONFIGURATION
DB_IP_ADDRESS=
DB_PORT=1521
DB_SID=P26184B
DB_USERNAME=COL27
DB_PASSWORD=
#BATCH CONFIGURAT
THREADPOOL_NAME=MT
NUMBER OF THREADS-5
BATCH_USER=SYSUSER
BATCH_LOG_DIR=/scratch/app/product/fmm/obpinstall/obp/fclogs/logs
#THREADPOOL CONFIGURATION
WEBLOGIC_SERVER_HOME=/scratch/app/product/fmm/wlserver
RMI PORT=2020
DOMAIN_PATH=/scratch/app/product/fmw/user_projects/domains/
DOMAIN_NAME=host_domain
CLUSTER NAME-IUT2
CLUSTER_MULTICAST_LISTNER_IP_ADDRESS=232.0.0.1
CLUSTER_MULTICAST_LISTNER_PORT=6660
TARGETTYPE=2
TARGETJMSSERVER-obphost_cluster1
```

- iv. Save config.properties file.
- v. Ensure that Admin server is in RUNNING state and Managed server is down.
- vi. Check if Admin server is running. Access Weblogic Admin Console. If Weblogic Admin Console returns below screen Admin server is up.

Figure 2-4 Weblogic Admin Console



vii. If Admin Server is down, start Admin Server. To start Admin server, use the following command:

```
${middleware home}/user projects/domains/{domain
name}/bin/ startWeblogic.sh
```


viii. To check if managed server is running, navigate to servers tab.

Figure 2-5 Summary of servers




ix. If managed server state is running, navigate to control tab and select managed server check box, click on shutdown button and select Force shutdown now.

Figure 2-6 Force shutdown



x. Click Yes on next screen.

Figure 2-7 Verify Server State



xi. If only Admin server is running, run installer using below command.

**Installation Completed..!** is prompted at the end.

#### b. GUI mode:

- i. Start the XManager application on the windows machine from where you have connected to the Host Server remotely and then click XPassive.
- ii. Export the XManager UI on the Host Server (Linux environment) using the following command:


Where, <IP> is the IP address of the windows machine.

- iii. Update config.properties in the TEMPDIR directory.
- iv. Set IS UI ENABLED=Y.
- v. Set IS\_STANDALONE = Y
- vi. Run installer using the following command:

java -jar collectioninstaller.jar

The Installer: Initial Details wizard page appears.

Figure 2-8 Installer: Initial Details



The **Installer: Initial Details** wizard page contains the following fields:

Table 2-6 Installer: Initial Details

Field	Description	
Operating System	Used to indicate the operating system on which you want to install the OBEDM Host Media Pack. The options are:	
	■ Linux	
	■ Windows	
	You can only integrate OBEDM with OBP on the Linux environment.	
Installation Directory	Used to specify the directory where you want to install the OBEDM Host Media Pack. It should be same as the installation directory where OBP Host Media pack is installed.	
	By default,/scratch/app/product/fmw/obpinstall/obpis specified in this field. You can change the path and directory name, if required.	
Generate Host Configuration	Used to deploy the OBEDMHost Media Pack components, if this option is checked.	
Generate UI Configuration	Used to deploy the OBEDMPresentation Media Pack components, if this option is checked.	
Generate Batch Configuration	Used to deploy the batch components used for configuring the batch server, if this option is checked.	

Field	Description	
	If you want to deploy the batch components, you must always select the Generate Host Configuration check box along with the Generate Batch Configuration check box.	
Generate Thread Pool Configuration	Used to deploy the threadpool components used for configuring the threadpool, if this option is checked.	
	If you want to deploy the threadpool components, you must always select the <b>Generate Host Configuration</b> check box and <b>Generate Batch Configuration</b> check box along with the <b>Generate Threadpool Configuration</b> check box.	
Customization Support Required	Used to enable the customization support, if CUSTOM_ SUPPORT is set to Y.	

- vii. Select the Generate Host Configuration check box.
- viii. If you want to deploy the batch components on the host server, select the **Generate Batch Configuration** check box.
- ix. If you want to deploy the batch components on the host server, select the **Generate Threadpool Configuration** check box.
- x. Click **Next**. The **Installer: Host Configuration** screen appears.

Figure 2-9 Installer: Host Configuration




The Installer: Host Configuration wizard page contains the following fields:

Table 2-7 Installer: Host Configuration

Field	Description
Host Logs Directory	Used to indicate the directory where the logs must be created on the host server. By default, /scratch/app/product/fmw/obpinstall/obp/fclogs/logs is specified in this field. You can change the path and directory name, if required.
Java Home Path	Used to indicate the directory where Oracle JDK is installed. By default, /scratch/app/product/jdk1.8.0_231 is specified in this field. You can change the path and directory name, if required.
Hibernate Path	Used to indicate the directory where Hibernate jars downloaded and copied jars from /lib/required/ from extracted hibernate-release-4.1.0. Final. zip package by default, /scratch/app/product/hibernate is specified in this field. You can change the path and directory name, if required. Installer will copy the jars from this directory to Third party directory.

- xi. Change the values in these fields, if required.
- xii. Click **Next**. The **Installer: Host DB Configuration** screen appears.

Figure 2–10 Installer: Host DB Configuration



The following fields appear in the **Installer: Host DB Configuration** screen:

Table 2–8 Installer: Host DB Configuration

Field	Description
Database IP address	Used to specify the database IP address. For example, 10.180.7.77.
Database port	Used to specify the database port. For example, 1521.
Database System ID (SID)	Used to specify the database SID. For example, ORA125.
Database user name	Used to specify the database user name.
Database user password	Used to specify the database password.
Host Datasource name	Used to specify the host NonXA data source name. For example, jdbc/FCBDataSource_NonXA.
Host IP address	Used to specify the host IP address. For example, 10.180.6.11
Host port	Used to specify the Host server WebLogic managed server port. For example, 8001.

xiii. Click **Next**. The **Installer: Batch Configuration** screen appears. This screen appears only if you have selected the **Generate Batch Configuration** option in the **Installer: Initial Details** screen.

JOB Collection Installer : Batch Configuration X ORACLE! OB Collection Installer: Batch Configuration Database IP address < DB IP Address > Database port 1521 V5DEV Database SID fcrhdevsails40 Database user name Database user password \*\*\*\*\* Thread pool name MT Number of threads 5 Batch user ID SYSUSER Batch log directory /scratch/app/product/fmw/obpinstall/obp/fclogs/logs Previous Next

Figure 2-11 Installer: Batch Configuration


The following fields appear in the **Installer: Batch Configuration** screen:

Table 2–9 Installer: Batch Configuration

Field	Description	
Database IP address	Used to specify the database IP address. For example, 10.180.7.77.	
Database port	Used to specify the database port. For example, 1521.	
Database System ID (SID)	Used to specify the database SID. For example, V5DEV.	
Database user name	Used to specify the database user name.	
Database user password	Used to specify the database password.	
Thread pool name	Used to specify the name of the thread pool. For example, MT.	
Number of threads	Used to specify the number of the threads that the thread pool can support. For example, 5.	
Batch user ID	Used to specify the batch user ID. For example, SYSUSER.	
Batch log directory	Used to specify the batch log directory. For example, /scratch/app/product/fmw/obpinstall/obp/fclogs/logs.	

xiv. Click **Next.** The **Installer: Threadpool Configuration** screen appears. This screen appears only if you have selected the **Generate Threadpool Configuration** option in the **Installer: Initial Details** screen.

Figure 2–12 Installer: Threadpool Configuration



The following fields appear in the **Installer: Threadpool Configuration** screen:

Table 2-10 Installer: Threadpool Configuration in config.properties


Field	Description	
Weblogic Server Home	Used to specify the weblogic server home path. For example, /scratch/app/product/fmw/wlserver.	
RMI Port	Used to specify the rmi port. For example, 2120.	
Host Domain Path	Used to specify the Host Domain Path. For example, /scratch/app/product/fmw/user_projects/domains/host_domain.	
Cluster Name	Used to specify the Threadpool cluster name. For example, Cluster1	
Cluster IP Address	Used to specify Threadpool cluster IP Address. For Example, 232.0.01	
Cluster Port	Used to specify Threadpool Cluster Port. For Example, 6660	

xv. Click **Next.** The **Installer: Confirm installation details** screen appears.

OB Collection Installer: Confirm installation details X ORACLE" OB Collection Installer: Confirm installation details -----Host Configuration ---Host logs directory: /scratch/app/product/fmw/obpinstall/obp/fclogs/logs Java home path : /scratch/app/product/jdk1.8.0\_101 Hibernate Jar Directory Path: /scratch/app/product/hibernate ---Host DB Configuration Is connection pooled : true Datasource name : jdbc/FCBDataSource\_NonXA Host IP address : Host port: 8001 ---Batch Configuration Is connection pooled : false Database IP address : Database port: 1521 Database SID : V5DEV Previous Generate

Figure 2-13 Installer: Confirm Installations Details

Figure 2-14 Installer: Confirm Installations Details



- xvi. Click Generate. The Installer: Installing screen appears.
- xvii. Click Done.
- 7. Delete below jar if present.


/scratch/app/product/fmw/wlserver/modules/cglib.cglib-nodep.jar

OR

/scratch/app/product/fmw/oracle\_common/modules/thirdparty/cglib-nodep-3.2.5.jar


- 8. Log in to Weblogic console and navigate to Data Sources-> OBP\_HOST\_DS\_NONXA -> Connection Pool.
- 9. Change Driver Class Name = oracle.jdbc.OracleDriver if it is different.

Figure 2-15 Data Source Connection Pool



- 10. Log in to Weblogic console and navigate to XML Registries.
- 11. Add new XML Registry Properties. If New button is disabled click on Lock & Edit button.


Figure 2-16 Add XML Registry



- 12. Change the following properties while adding XML Registry Properties and save changes.
  - Document Builder Factory = com.sun.org.apache.xerces.internal.jaxp.DocumentBuilderFactoryImpl

- SAX Parser Factory = com.sun.org.apache.xerces.internal.jaxp.SAXParserFactoryImpl
- Transformer Factory = com.sun.org.apache.xalan.internal.xsltc.trax.TransformerFactoryImpl

Figure 2–17 Settings for XML Registry




13. Click Next if available and Deploy XML Registry to managed server.

Figure 2-18 Deploy XML Registry



- 14. Log in to Weblogic console and navigate to Domain -> host\_domain (if multiple domains available) -> Security tab.
- 15. Verify Cross Domain Security Enabled check box is unchecked.

Figure 2–19 Host Domain Security




## 2.3 Configuring Weblogic Domain For Host

The following steps explain how to configure weblogic domain for host. These steps are already integrated in Silent mode of installer so continue from step 11. For GUI mode follow all steps.


- 1. To perform domain configuration, you must run Admin server. Ensure that managed server is not running.
- 2. To check if managed server is running, login to Weblogic console and navigate to servers tab.

Figure 2-20 Summary of servers




3. If managed server state is running, navigate to control tab and select managed server check box, click on shutdown button and select Force shutdown now.

Figure 2-21 Force shutdown




4. Click Yes on next screen.

Figure 2-22 Verify Server State



5. Check if Admin server is running. Access Weblogic Admin Console. If Weblogic Admin Console returns below screen Admin server is up.

Figure 2-23 Weblogic Admin Console



6. If Admin Server is down, start Admin Server. To start Admin server, use the following command:

```
${middleware__home}/user_projects/domains/{domain_
name}/bin/startHostAdminServer.sh
```

- 7. Browse the folder where you have extracted the Installation package.
- 8. Run the following command:

cd <PATH>/TEMPDIR

9. Execute the Install.sh file as below:

./Install.sh

The install file prompts for the following input:

Table 2–11 Configuring Weblogic Domain for Host

Field	Description
Select the Domain Name (Host / UI)	Indicates whether to configure Host or UI domain. To set up host domain, enter host.
Enter the Host IP/DNS (Domain Name Server)	Indicates the host IP address or DNS name.
Enter Admin Server Port	Indicates the port number of admin server.
Enter Weblogic home (WL_ HOME) directory (\${middleware_ home}/wlserver)	Indicates the home path of Weblogic. For example, /scratch/app/product/fmw/wlserver
Enter Deployment/Installation directory name	Used to specify the directory where you want to install the OBEDM Host Media Pack. By default, /scratch/app/product/fmw/obpinstall/obp is specified in this field. You can change the path and directory name, if required.
Enter Domain Directory Path where Domain is created (\${middleware_home}/user_projects/domain)	Indicates the generic domain_home path.
Enter Domain Name Directory (for example, host_domain)	Provide the domain name configured on weblogic and the directory present in domain_home.
Enter Weblogic console username	Indicates the username of weblogic console.
Enter Weblogic console password	Indicates the password of weblogic console.
Select the option (1 or 2) where you want to target JMS Module:  1. Server  2. Cluster	Select the option 1 or 2 as per requirement or configuration in OBP.
Enter the Name of Server where you want to target JMS module (for example, obphost_server1) -	If option 1 is selected then provide the name of the managed server.
Enter the Name of the Cluster where you want to target JMS module (For example, obphost_cluster1) -	If option 2 is selected then provide the name of the cluster.

10. Verify whether the information passed is correct and enter 'Y' to continue the configuration or 'N' to avoid domain configuration as shown in the following screenshot:

Figure 2-24 Domain Configuration: Confirm

```
| Ofssobp@ofss3131407/scratch/mstall|$ ./Install.sh
| Please provide the exact information as asked below
| Please select the Domain Name (Host / UI/ Host+Batch ) - Host+Batch
| Enter the Host server IP / DNS - 10.180.84.194
| Enter Admin server port - 7001
| Please enter Weblogic home (WI_HOME) directory ($(middleware_home)/wlserver) - /scratch/app/product/fmm/wlserver
| Enter Deployment/Installation directory name - /scratch/app/product/fmm/obpinstall/obp
| Enter Domain Directory Fath where Domain is created ($(middleware_home)/wser_projects/domain) - /scratch/app/product/fmw/user_projects/domains
| Enter Domain Name Directory (e.g. base_domain) - host_domain
| Enter Weblogic console username - weblogic
| Enter Weblogic console password - |
| Please select the option (1 or 2) where you want to target JMS Module - | 1. Server | 2. Cluster | -> 2 |
| Enter the Name of the Cluster where you want to target JMS module (e.g. obphost_cluster) - obphost_cluster1
| Hope the information provided is valid and we can proceed with domain configuration for Collection
| Please enter Y/N, so that we can continue with configuration... - |
```

- 11. Once you have completed the execution steps listed above, perform the following steps:
  - a. Connect to the database and execute below two statements to enable collection bootstrap.

You must set the collection bootstrap to true for the default management module to function properly.

```
update flx_fw_config_all_b set prop_value='true' where prop_id='collection.bootstrap' and category_id='root'; update flx_fw_config_all_b set prop_value='true' where prop_id='collection.webservice.bootstrap' and category_id='root';
```

b. Need to update setDomainEnv.sh file to append EXTRA\_JAVA\_PROPERTIES and append PRE\_CLASSPATH as following, if not present:

### **EXTRA\_JAVA\_PROPERTIES** before installation:

```
EXTRA_JAVA_PROPERTIES=" -
Djavax.xml.parsers.DocumentBuilderFactory=com.sun.org.ap
ache.xerces.internal.jaxp.DocumentBuilderFactoryImpl -
Djavax.xml.transform.TransformerFactory=com.sun.org.apac
he.xalan.internal.xsltc.trax.TransformerFactoryImpl -
Dweblogic.configuration.schemaValidationEnabled=false -
DentityExpansionLimit=1000 -Duser.home=${OBP_ORACLE_HOME}/config -Dfc.io.dir=${OBP_ORACLE_HOME} ${ORACLE_MEM_ARGS} ${EXTRA JAVA PROPERTIES}"
```

### After Installation:

```
EXTRA_JAVA_PROPERTIES=" -
Djavax.xml.parsers.DocumentBuilderFactory=com.sun.org.ap
ache.xerces.internal.jaxp.DocumentBuilderFactoryImpl -
```

```
Djavax.xml.transform.TransformerFactory=com.sun.org.apac
he.xalan.internal.xsltc.trax.TransformerFactorvImpl -
Djavax.xml.parsers.SAXParserFactory=com.sun.org.apache.x
erces.internal.jaxp.SAXParserFactoryImpl
Dweblogic.configuration.schemaValidationEnabled=false -
DentityExpansionLimit=1000 -Duser.home=${OBP ORACLE
HOME } / config - Dfc.io.dir = $ { OBP ORACLE HOME } $ { ORACLE MEM
ARGS} ${EXTRA JAVA PROPERTIES}"
```

#### Before Installation:

```
PRE CLASSPATH="${OBP ORACLE HOME}/config:${OBP ORACLE
HOME}/config/security/oaam:${PRE CLASSPATH}"
export PRE CLASSPATH
```

#### After Installation:

```
PRE CLASSPATH="${OBP ORACLE HOME}/config:${OBP ORACLE
HOME}/config/security/oaam:${OBP ORACLE
HOME } / obp.thirdparty.app.domain/APP-INF/lib/xmlparserv2-
12.1.0.2.0.jar:${PRE CLASSPATH}"
export PRE CLASSPATH
```

- Restart the admin server. To restart the Admin server, first stop the Admin server and then start it again.
  - a. To stop the Admin server, use the following command:

```
${middleware home}/user projects/domain/{domain
name}/bin/stopWeblogic.sh
```

Delete tmp, cache directories present inside the server directory.

For example,

```
${middleware home}/user projects/domain/{domain
name}/servers/{server name}/cache
${middleware home}/user projects/domain/{domain
name}/servers/{server name}/tmp
```

c. Delete the stage folder also if it is present under the following location:

```
${middleware home}/user projects/domain/{domain
name}/servers/{server name}/stage
```

Where {server name} indicates all the servers that are available in the domain, such as AdminServer, Managed server (obphost\_server1).

d. Then start Admin server by using the following command:

```
${middleware home}/user projects/domain/{domain
name } / bin/startWeblogic.sh
```

Start the managed servers.

Ignore the below error while starting host managed server.

ERROR (support.license.ModuleInfoCache) Module feature configuration not found; no modules will be disabled. To resolve this error add a feature configuration of type F1MD and associated options for disabled modules.

# 3 Installing the Presentation Media Pack

You must follow the steps mentioned below to install the Presentation Media Pack:

- 1. Install the Presentation Media Pack.
- 2. Configure the web logic domain.
- 3. Deploy the Collections module.

### 3.1 Prerequisites

You must install the following software prior to installing the Presentation Media Pack:

- OBP 2.11.0.0.0 Host Media Pack.
- OBP 2.11.0.0.0 Presentation Media Pack.
- OBEDM 2.11.0.0.0 Host Media Pack.

#### Note

Oracle JDK 1.8 Update 231 is required to run the OBEDM V2.11 installer. For more information on JDK installation, see Chapter 5 Installing Third-Party Software.

## 3.2 Installing the Presentation Media Pack

To install the Presentation Media Pack, you must download the installation package from the following link:

https://edelivery.oracle.com/

#### Note

Ensure that the node manager is not running on any of the target installation machines. Also, ensure that there are no processes running on the listener ports for any of the OBP domain servers that are to be installed.

To install the Presentation Media Pack, perform the following steps:

- 1. Download the appropriate OBEDM Media Pack. The media pack is available in this format: OBEDM\_V [Build Number].zip
- 2. Log in to the presentation server.
- 3. Create a temporary directory on the presentation server. For example, <TEMPDIR>.
- 4. Copy the OBEDM Media Pack OBEDM V[Build Number].zip downloaded from edelivery to presentation Linux server using WINSCP.
- 5. Copy the OBEDM Media Pack OBEDM\_V[Build\_Number].zip into the <TEMPDIR>.


6. Uncompress the OBEDM Media Pack OBEDM\_V[Build\_Number].zip by running the following commands:

```
cd <TEMPDIR>
unzip Collection_V[Build_Number].zip
```

The contents of the zip file are extracted in the TEMPDIR folder. The following files/folders are extracted:

- config.properties
- ouaf.properties
- data
- Install.sh
- Install\_Silent.sh
- collectioninstaller.jar
- collectionupgradeinstaller.jar

Figure 3-1 OBEDM\_V[Build\_Number].zip uncompressed



- 7. Collection installer operates in two modes. Go with either mode.
  - a. Silent Mode:
    - i. Update config.properties in the TEMPDIR directory.
    - ii. Set IS\_STANDALONE = Y
    - iii. Update below sections in config.properties as shown in Figure 2–3:
      - INSTALLER DETAILS
        - IS\_DEV\_ENV=false
        - IS\_UI\_ENABLED=N
      - INITIAL DETAILS
        - HOST\_CONFIG=N
        - UI\_CONFIG=Y

- BATCH\_CONFIG=N
- CUSTOM\_SUPPORT=N
- THREADPOOL\_CONFIG=N
- HOST CONFIGURATION
- UI CONFIGURATION
- DB CONFIGURATION

In config.properties: Initial Details section contains the following fields

Table 3-1 Installer: Initial Details in config.properties

Field	Description	
	Used to indicate the operating system on which you want to install the OBEDM Host Media Pack. The options are:	
Operating System	• Linux	
(ÓPERATING_ SYSTEM)	Windows	
	You can only integrate OBEDM with OBP on the Linux environment.	
Installation Directory	Used to specify the directory where you want to install the OBEDM Host Media Pack. It should be same as the installation directory where OBP Host Media pack is installed.	
(INSTALL_DIR)	By default, /scratch/app/product/fmw/obpinstall/obp is specified in this field. You can change the path and directory name, if required.	
Generate Host Configuration	Used to deploy the OBEDM Host Media Pack components, if this option is true.	
(HOST_CONFIG)	componente, il tille option is true.	
Generate UI Configuration (UI CONFIG)	Used to deploy the OBEDM Presentation Media Pack components, if this option is true.	
(01_0014110)	Used to deploy the batch components used for	
Generate Batch Configuration	configuring the batch server, if this option is true.	
(BATCH_ CONFIG)	If you want to deploy the batch components, you must always set the HOST_CONFIG and BATCH_CONFIG value to true.	
Generate Thread Pool Configuration	Used to deploy the threadpool components used for configuring the threadpool, if this option is checked.	

Field	Description	
(THREADPOOL_ CONFIG)	If you want to deploy the threadpool components, you must always set the HOST_CONFIG, BATCH_CONFIG and THREADPOOL_CONFIG value to true.	
Customization Support Required	Used to enable the customization support, if this option is true.	
(CUSTOM_ SUPPORT)		
	Used to specify domain name, possible options are:	
Damain nama	• UI	
Domain name (DOMAINNAME)	• HOST	
	HOST + BATCH	
	Select UI for presentation mediapack.	

In config.properties: Host Configuration section contains the following fields:

Table 3–2 Installer: Host Configuration in config.properties

Field	Description
Host IP address	Llandta annaife tha bant ID adduces. Fan account
(DB_IP_ ADDRESS)	Used to specify the host IP address. For example, 10.180.6.11.
Host port	Used to specify the Host server WebLogic managed
(DB_PORT)	server port. For example, 8001.
Host Logs Directory (HOST_LOG_DIR)	Used to indicate the directory where the logs must be created on the host server. By default, /scratch/app/product/fmw/obpinstall/obp/fclogs/logs is specified in this field. You can change the path and directory name, if required.
Java Home Path (JAVA_HOME)	Used to indicate the directory where Oracle JDK is installed. By default, /scratch/app/product/jdk1.8.0_231 is specified in this field. You can change the path and directory name, if required.
Hibernate Path (HIBERNATE_ JAR_DIR)	Used to indicate the directory where Hibernate jars downloaded and copied jars from /lib/required/ from extracted hibernate-release-4.1.0.Final.zip package by default, /scratch/app/product/hibernate is specified in this field. You can change the path and

Field	Description
	directory name, if required. Installer will copy the jars from this directory to Third party directory.
Host weblogic user name	
(HOST_ WEBLOGIC_	Used to specify the host weblogic username.
PASSWORD)	
Host weblogic password	
(HOST_ WEBLOGIC_	Used to specify the host weblogic password.
PASSWORD	
Host Datasource name	Used to specify the host NonXA data source name. For
(HOST_ DATASOURCE)	example, jdbc/FCBDataSource_NonXA.
Host Admin server port	
(HOST_ ADMINSERVERP ORT)	Used to specify the Host server WebLogic admin serve port. For example, 7001.

The following fields appear in the Installer: UI Configuration screen:

Table 3–3 Installer: UI Configuration in config.propertiesties

Field	Description
UI log directory	Used to specify the log directory for the presentation server. For example,
(UI_LOG_DIR)	/oracle/deployable/sails/fclogs/logs.
UI IP Address	Used to specify the host IP address. For example, 10.180.6.12.
(UI_IP_ADDRESS)	
UI Port (UI_PORT)	Used to specify the UI server WebLogic managed server port. For example, 8001.
UI Weblogic user name	Used to specify the UI WebLogic server admin use
(UI_WEBLOGIC_	name.

Field	Description	
USERNAME)		
UI Weblogic password		
(UI_WEBLOGIC_	Used to specify the UI WebLogic server admin password.	
PASSWORD)	•	
Host Datasource name	Used to specify the host NonXA data source name.	
(UI_DATASOURCE)	For example, jdbc/FCBDataSource_NonXA.	
UI Admin server port		
(HOST_ ADMINSERVERPORT)	Used to specify the UI server WebLogic admin server port. For example, 7001.	

In config.properties: DB Configuration section contains the following fields:

Table 3-4 Installer: DB Configuration in config.properties

Field	Description	
Database IP address	Used to specify the database IP address. For example,	
(DB_IP_ ADDRESS)	10.180.7.77.	
Database port	Used to specify the database port. For example, 1521	
(DB_PORT)		
Database System ID (DB_SID)	Used to specify the database SID. For example, ORA125.	
Database user name	Used to specify the database user name.	
(DB_USERNAME)		
Database user password	Used to specify the database password.	
(DB_PASSWORD)		


Figure 3-2 Installer: config.properties file

```
IS DEV ENV=false
OBP_HOST_LIB=ob.host.app/ob.app.host.coll/APP-INF/lib
OBP_THIRDPARTY_LIB=ob.host.app/ob.app.host.tp/APP-INF/lib
IS_UI_ENABLED=N
IS STANDALONE=Y
MINITIAL DETAILS
OPERATING SYSTEM =Linux
INSTALL_DIR=/scratch/app/product/fmw/obpinstall/obp
HOST CONFIG=N
UI_CONFIG=Y
BATCH_CONFIG=N
CUSTOM_SUPPORT=N
THREADPOOL CONFIG=N
DOMAINNAME=UI
#UI CONFIGURATION
UI_LOG_DIR=/scratch/app/product/fmw/obpinstall/obp/fclogs/logs
UI_IP_ADDRESS=
UI PORT-8001
UI WEBLOGIC USERNAME=weblogic
UI WEBLOGIC PASSWORD-
UI_DATASOURCE=jdbc/FCBDataSource_NonXA
UI_ADMINSERVERPORT=7001
#HOST CONFIGURATION
HOST_IP_ADDRESS=1
HOST_PORT=8001
HOST_LOG_DIR=/scratch/app/product/fmw/obpinstall/obp/fclogs/logs
JAVA_HOME=/scratch/app/product/jdk1.8.0_172
HIBERNATE_JAR_DIR=/scratch/ofssobp/Hibernate_tmp
HOST_WEBLOGIC_USERNAME=weblogic
HOST_WEBLOGIC_PASSWORD-
HOST ADMINSERVERPORT=7001
#DB CONFIGURATION
DB IP ADDRESS=
DB PORT=1521
DB_SID=P26184B
DB USERNAME=COL27
DB PASSWORD
HOST DATASOURCE-jdbc/FCBDataSource NonXA
#BATCH CONFIGURATION
THREADPOOL NAME-MT
NUMBER_OF_THREADS=5
BATCH_USER=SYSUSER
BATCH_LOG_DIR=/scratch/app/product/fmw/obpinstall/obp/fclogs/logs
#THREADPOOL CONFIGURATION
WEBLOGIC SERVER HOME=/scratch/app/product/fmw/wlserver
RMI PORT=2020
DOMAIN_PATH=/scratch/app/product/fmw/user_projects/domains/
DOMAIN_NAME=ui_domain
CLUSTER NAME=IUT2
CLUSTER_MULTICAST_LISTNER_IP_ADDRESS=232.0.0.1
CLUSTER MULTICAST LISTNER PORT=6660
TARGETTYPE=1
TARGETJMSSERVER=obpui_server1
```

- iv. Save config.properties file.
- v. Check if Admin server is running and Managed is down. Access Weblogic Admin

Console. If Weblogic Admin Console returns below screen Admin server is up.

Figure 3-3 Weblogic Admin Console



vi. If Weblogic Admin Server is down, start Admin server, use the following command:

```
${middleware__home}/user_projects/domain/${domain_
home}/bin/startWeblogic.sh
```

vii. If only Admin Server is up , run installer using below commands:

**Installation Completed**..! is prompted at the end.

#### b. GUI Mode:

- i. Run XManager application on Windows machine.
- ii. To export the XManager UI on the Linux environment, run the following command:


Where, IP is the IP address of your machine.

- iii. Update config.properties in the TEMPDIR directory
- iv. Set IS\_UI\_ENABLED=Y
- v. Set IS\_STANDALONE=Y
- vi. Run the following command to start the OBEDM installer. The Installer: Initial Details screen appears.

```
java -jar collectioninstaller.jar
```

vii. In the Installer: Initial Details screen, select the Installation directory and UI Configurations.

Figure 3-4 Installer: Initial Details




The following fields appear in the Installer: Initial Details screen:

Table 3-5 Installer: Initial Details

Field	Description	
Operating System	Used to specify the operating system platform on which the installation is to be done. For example, Linux.	
Installation Directory	Used to specify the directory where OBEDM 2.8 should be installed. Note that this is the same directory where the OBP presentation or host media packs are installed. For example, /oracle/deployables/sails/fclogs/logslogs.	
Generate Host Configuration	Deploys the host media pack components.	
Generate UI Configuration	Deploys the presentation media pack components.	
Generate Batch Configuration	Deploys the host media pack components. Note that host configuration must also be selected when batch components are to be enabled on the host that is used for configuring the batch server.	
Generate Thread Pool Configuration	Deploys the Host media pack components. Note that host configuration must also be selected when Thread Pool components are to be enabled on the host that is used for configuring the Thread Pool Node.	
Customization Support Required	Enables the customization support.	

viii. Click Next. The Installer: UI configuration screen appears.

Figure 3-5 Installer: UI configuration




The following fields appear in the Installer: UI Configuration screen:

Table 3-6 Installer: UI Configuration

Field	Description
UI log directory	Used to specify the log directory for the presentation server. For example, /oracle/deployable/sails/fclogs/logs.
Host IP address	Used to specify the host IP address. For example, 10.180.6.11.
Host port	Used to specify the Host server WebLogic managed server port. For example, 8001.
Host Weblogic user name	Used to specify the Host WebLogic server admin user name.
Host Weblogic password	Used to specify the Host WebLogic server admin password.
UI IP Address	Used to specify the host IP address. For example, 10.180.6.12.
UI Port	Used to specify the UI server WebLogic managed server port. For example, 8001.
UI Weblogic user name	Used to specify the UI WebLogic server admin user name.
UI Weblogic password	Used to specify the UI WebLogic server admin password.


ix. Click Next. The Installer: Confirm Installation details screen appears.

Figure 3-6 Installer: Confirm Installation Details



x. Click Generate.


Figure 3-7 Installer: Installing



- xi. Click Done
- 8. Log in to Weblogic console and navigate to XML Registries.
- 9. Add new XML Registry Properties

- 10. Change the following properties while adding XML Registry Properties and save changes.
  - Document Builder Factory = com.sun.org.apache.xerces.internal.jaxp.DocumentBuilderFactoryImpl
  - SAX Parser Factory = com.sun.org.apache.xerces.internal.jaxp.SAXParserFactoryImpl
  - Transformer Factory = com.sun.org.apache.xalan.internal.xsltc.trax.TransformerFactoryImpl

### Figure 3–8 XML Registry



- 11. In the Installer: Installing screen, confirm the following:
  - Under the InstallDir, collectionenv directory is created.
  - Collectionenv folder contains the properties folder and properties folder contains the web directory.

## 3.3 Configuring Weblogic Domain for Presentation Server

The following steps explain how to configure weblogic domain for presentation server. These steps are already integrated in Silent mode of installer so continue from step 8. For GUI mode follow all steps.

1. To perform domain configuration, Admin server must be running. Check if Admin server is running. Access Weblogic Admin Console. If Weblogic Admin Console returns below screen Admin server is up.

Figure 3-9 Weblogic Admin Console



2. If Weblogic Admin Server is down, start Admin server, use the following command:

\${middleware home}/user projects/domain/\${domain home}/bin/startWeblogic.sh

- 3. Browse the folder where you have extracted the Installation package.
- 4. Run the following command:

cd <PATH>/TEMPDIR

- 5. Execute the Install.sh file as mentioned below:
  - ./Install.sh
- 6. The install file prompts for input. Enter the following details when prompted:

Table 3–7 Configuring Weblogic Domain for Presentation

Field	Description
Please select the Domain Name (Host / UI)	Enter UI to setup host domain.
Enter the Host IP/DNS	Enter UI IP address or DNS name.
Enter Admin server port	Enter Admin server port number.
Please enter Weblogic home (WL_ HOME) directory (\${middleware_ home}/wlserver)	Its Weblogic home path. For example, /scratch/app/product/fmw/wlserver
Enter Deployment/Installation directory name	Used to specify the directory where you want to install the OBEDM Host Media Pack. By default, /scratch/app/product/fmw/obpinstall/obp is specified in this field. You can change the path and directory name, if required.

Field	Description
Enter Domain Directory Path where Domain is created (\${middleware_home}/user_projects/domain)	Its generic domain_home path.
Enter Domain Name Directory (for example, base_domain)	Provide the domain name configured on weblogic and the directory present in domain_home.
Enter Weblogic console username	Username of weblogic console.
Enter Weblogic console password	Password of weblogic console.
Enter Database URL	Provide database connection URL.
Enter Database user name	Provide database user name.
Enter Database password	Provide password for the user.
Select the option (1 or 2) where you want to target Datasource and CollectionWeb application:	Select the option 1 or 2 as per requirement or configuration in
1. Server	OBP.
2. Cluster	
Enter the Name of Server where you want to target data source and collectionweb application (for example, obpui_server1)	If option 1 is selected then provide the name of the managed server.
Enter the Name of Cluster where you want to target data source and collectionweb application (for example, obpui_cluster01)	If option 2 is selected then provide the name of the cluster.

7. Verify whether the information passed is correct and enter 'Y' to continue the configuration or 'N' to avoid domain configuration.

Figure 3–10 Domain Configuration: Confirm

```
collection@collection-linux:/scratch/app/product/fmw/obpinstall_test/Installer
  ollection@collection-linux Installer]$ sh Install.sh
 Please provide the exact information as asked below
Please select the Domain Name (Host / UI/ Host+Batch )- UI
 Enter Admin server port - 7001
 nter Domain Directory Path where Domain is created (${middleware_home}/user_projects/domain)-/scratch/app/product/fmw/user_projects/domains
 nter Weblogic console username - weblogic
 Inter Weblogic console password -
 Enter Databse url (DB_IP:PORT/SID eg: 10.10.10.10:1521/HR) - 10.180.84.34:1523/P843422B
 nter Databse username - OBPEXA271
 Enter Databse password -

    Server
    Cluster

 nter the Name of Cluster where you want to target data source and collectionweb application (e.g. obpui_cluster1) - obpui_cluster1
 ope the information provided is valid and we can proceed with domain configuration for Collection
  lease enter Y/N, so that we can continue with configuration... - Y
```

Figure 3-11 Domain Configuration: Proceeding with the Process

```
lease provide the exact information as asked below
lease select the Domain Name (Host / UI/ Host+Batch ) - UI
nter Admin server port - 7001
lease enter Weblogic home (WL_BOME) directory (%(middleware_home)/wlserver
)-/scratch/app/product/fmw/vlserver
nter Deployment/Installation directory name - /scratch/app/product/fmw/obpinstall/obp
nter Domain Name Directory (e.g. base domain) - ui domain
nter Weblogic console username - weblogic
nter Weblogic console password -
lease select the option (1 or 2) where you want to target CollectionWeb application = 1. Server 2. Cluster
nter the Mane of Server where you want to target data source and collectionweb application (e.g. obpui server1) - obpui server1
lease enter T/N. so that we can continue with configuration ... - v
ollection web deployment is successful, please re-start the servers now
ill be adding entry into setDomainEnv.sh
ofssobp@mum00bgr Collections]$
```

8. Need to update setDomainEnv.sh file to append EXTRA\_JAVA\_PROPERTIES, if not present.

### **EXTRA\_JAVA\_PROPERTIES** before installation:

```
EXTRA_JAVA_PROPERTIES=" -
Djavax.xml.parsers.DocumentBuilderFactory=com.sun.org.apache.
xerces.internal.jaxp.DocumentBuilderFactoryImpl -
Djavax.xml.transform.TransformerFactory=com.sun.org.apache.xa
lan.internal.xsltc.trax.TransformerFactoryImpl -
Dweblogic.configuration.schemaValidationEnabled=false -
DentityExpansionLimit=1000 -Duser.home=${OBP_ORACLE_HOME}/config -Dfc.io.dir=${OBP_ORACLE_HOME} ${ORACLE_MEM_ARGS}}$
${EXTRA JAVA PROPERTIES}"
```

### After Installation:

```
EXTRA_JAVA_PROPERTIES=" -
Djavax.xml.parsers.DocumentBuilderFactory=com.sun.org.apache.
xerces.internal.jaxp.DocumentBuilderFactoryImpl -
Djavax.xml.transform.TransformerFactory=com.sun.org.apache.xa
lan.internal.xsltc.trax.TransformerFactoryImpl -
Djavax.xml.parsers.SAXParserFactory=com.sun.org.apache.xerces
.internal.jaxp.SAXParserFactoryImpl
Dweblogic.configuration.schemaValidationEnabled=false -
DentityExpansionLimit=1000
-Duser.home=${OBP_ORACLE_HOME}/config -Dfc.io.dir=${OBP_
ORACLE HOME} ${ORACLE MEM ARGS} ${EXTRA JAVA PROPERTIES}"
```

- 9. Restart Admin server. Before restarting, stop Admin server.
  - a. To stop the Admin server, use the following command:

```
${middleware_home}/user_projects/domain/{domain_
name}/bin/stopWeblogic.sh
```

b. Delete tmp, cache directories present inside the server directory.

For example,

```
${middleware_home}/user_projects/domain/{domain_
name}/servers/{server_name}/cache
${middleware_home}/user_projects/domain/{domain_
name}/servers/{server_name}/tmp
```

Where {server\_name} indicates all the servers that are available in the domain, such as AdminServer, Managed server (obphost\_server1).

c. Then start Admin server by using the following command:

```
${middleware_home}/user_projects/domain/{domain_
name}/bin/startWeblogic.sh
```

10. Once the Admin server is up, then start the managed servers.

## 3.4 Verifying the Presentation Server Deployment

Before you start verifying the presentation server deployment, configure SYSUSER on OID server as per the steps mentioned in Chapter 6 User Creation.

To verify successful deployment, log on to the following URL:

http://IPADDRESS:PORT/CollectionAdmin/cis.jsp

Following are the components of the URL:

Table 3–8 Verifying the Presentation Server Deployment

Components	Description	
IPAddress	Indicates the IP address of the presentation WebLogic server.	
Port	Indicates the Presentation WebLogic managed server port number.	

For example,

http://10.180.10.11:8001/CollectionAdmin/cis.jsp



# 4 External Interface Configuration

This chapter explains the OBEDM external interface configuration details.

## 4.1 Oracle Identity Manager (OIM)

You can download the OIM Adapter configuration files from the following location:

http://edelivery.oracle.com

To extract the OIM Adapter configuration files, perform the following steps:

- 1. Download the appropriate OBEDM Media Pack. The media pack is available in the following format: OBEDM V[Build Number].zip
- 2. Copy the OBEDM\_V[Build\_Number].zip into the <TEMPDIR>.
- 3. Uncompress OBEDM\_V[Build\_Number].zip by running the following commands:

```
cd <TEMPDIR>
unzip OBEDM V[Build Number].zip
```

The contents of the zip file are extracted in the TEMPDIR folder. The following files and folders are extracted:

- config.properties
- ouaf.properties
- data
- Install.sh
- collectioninstaller.jar
- collectionupgradeinstaller.jar
- 4. You can locate the OIM adapter configuration files under the following location: data/extxface/OIM/ folder. Following files are available:
  - collections\_oim\_export.xml
  - com.ofss.fc.extxface.oim.jar
  - com.ofss.fc.extxface.wsdl.client.jar

### Note

For detailed configuration of the OIM Adapter, see the Oracle Banking Enterprise Default Management User Provisioning Guide.



# 5 Installing Third-Party Software

You must install the Oracle JDK before you install the OBEDM media packs, if not already installed on the servers.

## 5.1 Installing Oracle Java Development Kit (JDK)

You must install the JDK for 64-bit Linux operating system before you install presentation or host media pack.

To download, install and use JDK, follow the steps mentioned below:

1. Download the JDK file to any directory for which you have write permission. The file appears in the following format:

jdk-8u

<version>-linux-x64.bin

<version> jdk-8u101-linux-x64.bin

#### Note

Only the root user has the privilege to displace the system version of the Java platform that is supplied by Linux.


2. To set the execute permission, run the following command:

```
% chmod +x 8u <version> -linux-x64.bin
```

- 3. Change the directory location to the location where you want to install the files.
- 4. To execute the self-extract binary file, run the following command and then press Enter:

```
% ./jdk-8u <version> -linux-x64.bin
```

5. You must agree to the terms of the binary code license. This installs the JDK files in the following directory under the current directory: jdk.8.0\_<version>



# **6 User Creation**

This chapter provides information about user creation. This can be done in either of the following ways:

- User Creation with Oracle Internet Directory (OID)
- User Creation with Local Security (in database)


### 6.1 User Creation with OID

SYSUSER has to be created in Oracle Internet Directory (OID). It is used as default login for the Collections Admin. Follow the below steps to create a user:

1. Access the appropriate ODSM and select the required OID.


ODSM URL: <OID\_IP>:7005/odsm.

Figure 6-1 Opening ODSM



2. Log in to the OID.

Figure 6-2 Log in to OID



Click the Data Browser tab, in the Data tree panel navigate to Root -> dc=com -> dc-oracle -> dc=in -> cn=Users as shown in below screen. Right click on any user already present and select Create option.

Figure 6–3 Navigating to Data Browser Tab





Figure 6–4 Creating New Entry



- 4. Create new entry in **Users** tab and add the following Object classes:
  - top
  - person
  - fcPerson
  - organisationalPerson
  - inetOrgPerson
  - orclUser
  - orclUserV2

Figure 6-5 Adding Object Classes: Top




Figure 6-6 Adding Object Classes: Person






Figure 6-7 Adding Object Classes: Oracle User




5. Select the Parent of the entry **(Distinguished Name** DN) by clicking the **Browse** button. Select the path as Root -> dc=com -> dc-oracle -> dc=in -> cn=Users

Figure 6-8 Selecting Distinguished Name




6. Click the **Next** button.

Figure 6-9 Selecting Entry Properties




7. Select the **Relative Distinguished Name** as **uid**. Then enter the values of cn, sn and uid as **SYSUSER**.

Figure 6-10 Selecting Mandatory Properties




8. Click Next. The new user is created in OID and a message appears as shown in Figure 6–11.

Figure 6-11 Status Message




9. Select that user 'uid=SYSUSER' from the Data tree list.

Figure 6-12 Selecting the User




10. Click the Attributes tab, and then click the Add symbol under Optional Attributes section.

Figure 6-13 Attributes Tab




11. Add the 'userPassword' attribute from the All Attribute list and click the Add Attribute button.

Figure 6-14 Adding User Password




12. Enter the value in the **userPassword** field and click the **Apply** button in right hand corner.

Figure 6-15 Setting User Password




The confirmation message appears as "Changes have been applied successfully." as shown in Figure 6–16.

Figure 6-16 Confirm Message




13. Once user is created, add it into **Administrator group**. Navigate in Data tree as Root -> dc=com -> dc-oracle -> dc=in -> cn=Groups.

Figure 6-17 Adding to Administrator Group




14. Click the **Attributes** tab and click the **Add** button in 'uniqueMember' table. Add the below entry into it. uid=SYSUSER,cn=users,dc=in,dc=oracle,dc=com

Figure 6-18 Attributes Tab



 Click the **Apply** button. The confirmation message appears as "Changes have been applied successfully."

Figure 6-19 Confirmation message



16. Run the following query to ensure that Collection Dashboard is shown as the default page after logging in.

```
update flx_fw_config_all_b set prop_value='Role' where prop_
id='collection.roles' and CATEGORY_ID='BROPConfig';
```

where **Role** = configured user role in step 14.

# 6.2 User Creation with Local Security (in database)


SYSUSER has to be created in Oracle database using the following screens provided in the application. It is used as default login for the Collections Admin. Follow the below steps to create a user:

1. Using the **Define Application Role (Fast Path: SM002)** page, you can define the application roles.

To create an application role:

a. Navigate to the SM002 page and click Update.

Figure 6-20 Define Application Role page




- b. Click Add.
- c. Enter the application role details as required.
- d. Click **OK** to save the details.
- 2. Using the **Define Enterprise Role (Fast Path: SM003)** page, you can define the enterprise role and link it to an application role.

To create an enterprise role:

a. Navigate to the SM003 page and click Update.

Figure 6-21 Define Enterprise Role page




- b. Click Add.
- c. Enter details for the required enterprise role.
- d. Click **OK** to save the details.
- 3. Using the Manage User Creation (Fast Path: SM004) page, create a user with the specific enterprise roles.

To create a user:


a. Navigate to the SM004 page.

Figure 6-22 Manage User Creation page - Personal and Profile section



- b. Click Create.
- c. Enter details in the Personal and Profile sections.
- d. Enter details in Others section and specify the appropriate branch details and enterprise roles for the user.

Figure 6-23 Manage User Creation page - Others section




- e. Click **OK** to save the details.
- 4. Using the **Pass Policy Management (Fast Path: SM001)** page, you can configure the password policies to be managed by the bank. You can define all the perquisites for password creation during user creation.

### To create a password policy:

a. Navigate to the SM001 page and click Update.

Figure 6-24 Pass Policy Management page



- b. Enter the password policy details.
- c. Click **OK** to save the details.



# 7 Threadpool Configuration

This chapter provides information about threadpool configuration.

# 7.1 Manage Requisite Files in lib

To manage the requisite files in lib:

- 1. Go to Putty and change directories to ../obpinstall/obp/collectionenv/standalone/lib/ext.
- 2. If wlfullclient.jar, dms.jar and ojdl.jar are present in this directory, then go to step 8.
- 3. If this directory is empty, change directories to the server/lib directory.
  - ../app/product/fmw/wlserver/server/lib
- 4. Use the following command to create wlfullclient.jar in the server/lib directory:

java -jar wljarbuilder.jar

#### Figure 7–1 Command to Create wlfullclient.jar

```
-->(1)/(37265)//scratch/app/product/fmw/modules/com.bea.core.htt
p.pubsub.mbean_1.7.0.0.jar
Integrating jar <--(1)/(37269)/(4)//scratch/app/product/fmw/modules/com.bea.core
.http.pubsub.mbean 1.7.0.0.jar
Integrating jar -->(1)/(37269)//scratch/app/product/fmw/modules/com.bea.core.dia
gnostics.accessor_1.5.0.0.jar
(integrating jar <--(1)/(37365)/(96)//scratch/app/product/fmw/modules/com.bea.cor</pre>
e.diagnostics.accessor_1.5.0.0.jar
Created new jar file: /scratch/app/product/fmw/wlserver 10.3/server/lib/wlfullcl
[ofssobp@mum00are lib]$
```

- 5. Copy the generated wlfullclient.jar to path:
  - ../obpinstall/obp/collectionenv/standalone/lib/ext/
- 6. Copy dms.jar to path ../obpinstall/obp/collectionenv/standalone/lib/ext from
  - ../app/product/fmw/oracle common/modules/oracle.dms/
- 7. Copy ojdl.jar to path ../obpinstall/obp/collectionenv/standalone/lib/ext from
  - .. app/product/fmw/oracle\_common/modules/oracle.odl/
- 8. Add below properties to **setDomainEnv.sh** if not present.

```
WLS_JDBC_REMOTE_ENABLED="-Dweblogic.jdbc.remoteEnabled=true"
export WLS_JDBC_REMOTE_ENABLED
```

9. In ThreadpoolEnv.sh file at ../obpinstall/obp/collectionenv/standalone/bin, verify that the following properties are according to the environment:

export JAVA\_HOME=/scratch/app/product/jdk1.8.0\_231/jre

export SPLEBASE..../product/fmw/obpinstall/obp/collectionenv
export OBPBASE=...../product/fmw/obpinstall/obp
export com\_ofss\_standlone\_executor\_filterId=XXXXXX

#specify com\_ofss\_standlone\_executor\_filterId property if there is any filter defined.

#Check from FLX\_RL\_FILTER\_TEXTS TABLE in DB for filter defined.

- 10. Verify threadpoolworker.properties. To modify threadpoolworker.properties:
  - a. Go to the path:

../obpinstall/obp/collectionenv/standalone/config/threadpoolworker.properties

b. Verify the rmi\_port and Server Name--

com.splwg.grid.distThreadPool.threads.ThreadPool\_Name=<Maximum Thread count>
spl.runtime.management.rmi.port=<rmi\_port>
spl.runtime.management.connector.url.default=service:jmx:rmi:///jndi/rmi://< server-name>:<rmi\_port>/spl/fw/jmxConnector

Where:

rmi\_port= RMI port used for JMX. To manage each instance of the pool an unique port number should be used.

server-name = host server IP

For Example:

com.splwg.grid.distThreadPool.threads.STANDALONE\_TP=40

spl.runtime.management.rmi.port=9999

spl.runtime.management.connector.url.default=service:jmx:rmi:///jndi/rmi://XX.XX.XX.XX:

9999/spl/fw/jmxConnector

XX.XX.XX.XX= host IP

- 11. Modify spl.properties. To modify spl.properties:
  - a. Go to the path: ../obpinstall/obp/collectionenv/standalone/config/spl.properties
  - b. Add below property:

spl.runtime.batch.L2CacheMode=OFF

Figure 7-2 Standalone lib



# 7.2 Recommendations for Threadpool Memory Configuration

Consider setting the Threadpool JVM memory arguments as mentioned below. This needs to be modified in threadpoolworker.sh

MEM ARGS="-Xms4096m-Xmx8192m -XX:MaxPermSize=1024m -XX:+UseParalleIGC -XX:ParallelGCThreads=16"

# 7.3 Start Threadpoolworker

To start the threadpool worker:

- 1. Open the putty and go to ..../OBEinstall/OBE/collectionenv/standalone/bin
- 2. Run the command:
  - ../threadpoolworker.sh
    - Logs related to threadpool are generated as threadpoolworker.2017XXX.XXX.log and ThreadPool.log along with collection.log and specific Batch related logs will be generated at:
      - ../fmw/OBEinstall/OBE/fclogs/logs
    - Logs of OBE related to ThreadPool will be generated at:
      - .../fmw/OBEinstall/OBE/fclogs/logs/standalone/obp/logs (Use root collection log path in place of .../fmw/OBEinstall/OBE/fclogs)

## 7.4 Verification

To verify OBE context is successfully up:

1. Check threadpoolworker.2017XXX.XXX.log and search for Done with OBE initialisation.

Figure 7–3 ThreadPool Worker Log

```
Java Hotspot(M) 64-Bit Server W warning: ignoring option MaxPermSize=4096m; support was removed in 8.0 Listening for transport dt_socket at address; 8990 Executing opp initialisation block.

Session Context used during opp initialisation block.

Session Context used during opp initialisation sessionContext [bankCode=10, transactionBranch=1000, localDateTimeText=20170331114058, externalRef [EL Severe]: 2017-03-31 11:40:58.937--Failed to load: orm/eclipselink/cfg/core-adapter-query-mapping.cfg.xml [EL Warning]: 2017-03-31 11:40:59.016--warning: cant find bundle for base name orm/eclipselink/cfg/cz-module-cfg, locale en_US [EL Warning]: 2017-03-31 11:40:59.016--warning: cant find bundle for base name orm/eclipselink/cfg/cz-module-cfg, locale en_US System property [org. owasp.esapi.opstemm] is not set Astempting to load ESAPI.properties as resource file via file I/O. Not found in 'org. owasp.esapi.resources' directory or file not readable: /scratch/app/product/fmw/obpinstall/obp/fclogs/logs/logs/logs/spaI.properties as resource file via file I/O. Not found in 'ystemResource Directory/resourceDirectory (this should never happen): /scratch/app/product/fmw/obpinstall/obp/fclogs/logs/files/scra Not found in 'ystemResource Directory/resourceDirectory (this should never happen): /scratch/app/product/fmw/obpinstall/obp/fclogs/logs/files/scra Not found in 'ystemResource Directory/resourceDirectory (this should never happen): /scratch/app/product/fmw/obpinstall/obp/collectionc Attempting to load ESAPI.properties via file I/O failed. Exception was: java.io.rileNotomodexception Attempting to load SaPI.properties via file LCASSPATH from '.esapi/' using current thread context class loader!

Attempting to load validation.properties wia file I/O. Not found in 'org.owasp.esapi.resources' directory or file not readable: /scratch/app/product/fmw/obpinstall/obp/fclogs/logs/siles/scra Not found in 'ystemResource Directory/resourceDirectory (this should never happen): /scratch/app/product/fmw/obpinstall/obp/fclogs/logs/files/scra Not f
                     🗔 🙎 🖟 🖟 🗶 🔠 💆 😉 🛗 📞 🍪 🖷 | Encoding ▼ 🗆 Color ▼ 🍪 🕢
         Done with OBP initialisation...

**SEF41: Class path contains multiple SLE41 bindings.

**SLE41: Class path contains multiple SLE41 bindings.

**SLE41: Class path contains multiple SLE41 bindings.

**SLE41: Found binding in [jar:file:/scratch/app/product/fmw/obpinstall/obp/collectionenv/standalone/lib/spl-shared-4.3.0.1.0.jar!/org/slf4]/impl/st

**SLE41: Found binding in [jar:file:/scratch/app/product/fmw/obpinstall/obp/obp.host.app.domain/APP-INF/lib/spl-shared-4.3.0.1.0.jar!/org/slf4]/impl

**SLE41: Found binding in [jar:file:/scratch/app/product/fmw/obpinstall/obp/obp.thirdparty.app.domain/APP-INF/lib/slf4j-jdk14-1.6.1.jar!/org/slf4]/impl

**SLE41: Actual binding is for type [org.slf4].impl.SLE41]**

**SLE41: Actual binding is of type [org.slf4].impl.S
```

2. If filter is configured in ThreadpoolEnv.sh, with com\_ofss\_standlone\_executor\_filterId property then

check filter logs for verification.

#### Figure 7-4 Executing OBE Initialisation Block

```
Java HotSpot(TM) 64-Bit Server vM warning: ignoring option MaxPermSize=4096m; support was removed in 8.0
Listering for transport dt.socket at address: 8990
SesSion Context used during OBP initialisation sessionContext [bankCode=10, transactionBranch=1000, localDaterimerext=20170331114058, externalRef [EL Severe]: 2017-03-31 11:40:58.937-Failed to load: orm/eclipselink/cfg/core-adapter-query-mapping.cfg.xml [EL warning]: 2017-03-31 11:40:59.014-warning: cant find bundle for base name orm/eclipselink/cfg/cz-module-cfg, locale en_us [EL warning]: 2017-03-31 11:40:59.014-warning: cant find bundle for base name orm/eclipselink/cfg/cz-module-cfg, locale en_us [EL warning]: 2017-03-31 11:40:59.015-warning: cant find bundle for base name orm/eclipselink/cfg/cz-module-cfg, locale en_us System property [org. owasp. esapl. posteam] is not set attempting to load ESAPI.properties via file I/O.

Attempting to load ESAPI.properties via file I/O. Not found in 'org.owasp.esapl.resources' directory or file not readable: /scratch/app/product/fmm/obpinstall/obp/fclogs/logs/FSAPI.properties via file I/O failed. Exception was: java.io.FileNotFoundException

Attempting to load ESAPI.properties via the CLASSPATH from '.esapl/' using current thread context class loader! Succissfully LOADED ESAPI.properties via the CLASSPATH from '.esapl/' using current thread context class loader! Succissfully LOADED ESAPI.properties via the CLASSPATH from '.esapl/' using current thread context class loader! Succissfully LOADED ESAPI.properties via the CLASSPATH from '.esapl/' using current thread context class loader! Succissfully Volade on properties via file I/O failed. Exception on the context class loader! Succissfully Volade on properties via file I/O failed. Succissfully Vola
```

To verify whether the Threadpoolworker has started successfully:

1. Check for connection to:

service:jmx:rmi:///jndi/rmi://<server-name>:<rmi port>/spl/fw/jmxConnector

By using any VM tool (For example, jconsole).

### Note

Ensure this poolname is same as what is mentioned in threadpoolworker.properties (as com.splwg.grid.distThreadPool.threads.STANDALONE\_TP=40) and also in jconsole.




Figure 7-5 Verify Threadpool Worker: Check Connection

2. Search for the following text with latest time stamp in ThreadPool.log:

#### In Distributed Mode:

INFO (grid.node.DistributedGridNode) Distributed node 7621b973d7669cd8:3cdc534f:15affeb62a5:-7ff6 joined grid

### In Clustered Mode:

INFO (support.cluster.ClusteredNode) Clustered node with member id=3 has been initialized on cluster: CLUSTER1

3. Verify that the following properties are present in <INSTALLATION\_DIR>/ collectionenv/standalone/bin/spl.properties.

If HOST OS is Linux

export SERVER\_ROLE\_BATCH=true

export OBPBASE=<INSTALLATION DIR PATH>

If Host OS is Windows

set SERVER\_ROLE\_BATCH=true

set OBPBASE=<INSTALLATION DIR PATH>

# 7.5 Submit the Batch

Run the CSMB and CASETRAN batch with Thread pool name specified in **threadpoolworker.properties** (as com.splwg.grid.distThreadPool.threads.STANDALONE\_TP=40)

by using -p


For example:

./submitjob.sh -b CASETRAN -t 0 -c 8 -p STANDALONE\_TP

Where:

- -c No. of threads
- -t Thread Number
- -p ThreadPool Name

Figure 7-6 Submit the Batch



# 7.6 Stop Threadpoolworker

**jmxbatchclient.sh:** This script will wrap the JMXCommandLineClient java class so that it can be executed just like any operating scripts. The only option required is the JMX URL to connect. By default, it will only display information. For example, supplying only the required JMX connection information would result in as follows:

```
Options: -j
service:jmx:rmi:///jndi/rmi://myserver:9999/spl/fw/jmxConnector
Connecting to
service:jmx:rmi:///jndi/rmi://myserver:9999/spl/fw/jmxConnector
ActiveGridNode
```

```
threadPools=[DEFAULT:5, SCHEDULER_DAEMON_THREAD_POOL:1, LOCAL_
THREAD_POOL:b9835d11f15fd71b:1df6824f:120011dc94e:-8000:0]
BatchThread ZZQABAT2 1 of 1.36
```

This shows that the thread pools defined, separated by commas, and that there is currently an active batch thread.

# 7.7 Command-Line Options

The following options can be specified when executing script **jmxbatchclient**.usage:

```
com.splwg.base.api.batch.JMXCommandLineClient
-h Show this usage information.
-j <JMX URL> The JMX URL to connect to.
-d display details
-k Kill threadpool worker.
-s Display summary
```

#### Show usage (-h)

Display the available options and their descriptions.

### Show usage (-j)

Required. Specify the JMX URL to connect to. This should match the spl.runtime.management.connector.url.default property specified in the threadpoolworker.properties.

jmxbatchclient.sh -j service:jmx:rmi:///jndi/rmi://myserver:9999/spl/fw/jmxConnector

#### Display details (-d)

Display the details of the currently active threads.

```
Options: -j
service:jmx:rmi:///jndi/rmi://myserver:9999/spl/fw/jmxConnector -d
Connecting to
service:jmx:rmi:///jndi/rmi://myserver:9999/spl/fw/jmxConnector
ActiveGridNode
threadPools=[FJOCSON-US:5, SCHEDULER DAEMON THREAD POOL:1, LOCAL
THREAD POOL:b9835d11f15fd71b:1df6824f:120011dc94e:-8000:0]
BatchThread ZZQABAT2 1 of 1.36
ElapsedTime = 0 yrs. 0 days 00:00:20
BatchCd = ZZOABAT2
ThreadCount = 1
ThreadNumber = 1
RerunNumber = 0
ProcessDate = 2009-03-13
MaximumCommitRecords = 200
MaximumTimeoutMinutes = 0
UserId = SYSUSER
LanguageCd = ENG
SoftParameters = []
MaxExecutionAttempts = 1
DateTimeStarted = 2009-03-13-11.54.02
```

```
DistThreadPool = FJOCSON-US
BatchNumber = 4
Status = Running
ProgramType = Java
ProgramName = com.splwg.cm.domain.qa.batch.QaBatch2
RunType = New Run
```

### Kill threadpoolworker (-k)

Specifying this option will result in the cancellation of all currently running threads and the stoppage of the threadpoolworker process.

After successful stoppage of threadpoolworker message will be displayed on command line as:

"Successfully stopped threadpoolworker..."

"Distributed Grid stopped successfully"

### Display summary (-s)

Display the summary of the currently active threads is a listing format.

```
Options: -j
service:jmx:rmi:///jndi/rmi://myserver:9999/spl/fw/jmxConnector -s
Connecting to service:jmx:rmi:///jndi/rmi://fjocson-
us:9999/spl/fw/jmxConnector
ActiveGridNode
threadPools=[FJOCSON-US:5, SCHEDULER_DAEMON_THREAD_POOL:1, LOCAL_
THREAD_POOL:b9835d11f15fd71b:-60bf2fc1:120115996cc:-8000:0]
JMX Id DistThreadPool BatchNumber
DatTimeStarted ElapsedTime
BatchThread_ZZQABAT1_1_of_1.29 FJOCSON-US 32 2009-03-16-17.07.29 0
yrs. 0 days 00:03:49
```