

## **Oracle® C++ Call Interface**

Programmer's Guide,

11g Release 1 (11.1)

**B28390-07**

February 2013

Oracle C++ Call Interface Programmer's Guide, 11g Release 1 (11.1)

B28390-07

Copyright © 1999, 2013, Oracle and/or its affiliates. All rights reserved.

Primary Authors: Rod Ward, Roza Leyderman

Contributors: Sandeepan Banerjee, Subhranshu Banerjee, Kalyanji Chintakayala, Krishna Itikarlapalli, Shankar Iyer, Maura Joglekar, Toliver Jue, Ravi Kasamsetty, Srinath Krishnaswamy, Shoaib Lari, Geoff Lee, Chetan Maiya, Rekha Vallam

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information on content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

---

---

# Contents

<b>Preface</b> .....	xxxv
Audience.....	xxxv
Documentation Accessibility .....	xxxv
.....	xxxv
Related Documents .....	xxxv
Conventions .....	xxxvi
<b>What's New in Oracle C++ Call Interface?</b> .....	xxxvii
New Features for Oracle Database 11g Release 1 (11.1) .....	xxxvii
<b>1 Introduction to OCCI</b>	
<b>Overview of OCCI</b> .....	1-1
Benefits of OCCI.....	1-2
Building an OCCI Application.....	1-2
Functionality of OCCI .....	1-3
Procedural and Nonprocedural Elements.....	1-3
<b>Processing of SQL Statements</b> .....	1-4
DDL Statements.....	1-4
Control Statements.....	1-5
DML SQL Statements .....	1-5
Queries.....	1-5
<b>Overview of PL/SQL</b> .....	1-6
<b>Special OCCI/SQL Terms</b> .....	1-6
<b>Object Support</b> .....	1-7
Client-Side Object Cache.....	1-8
Runtime Environment for Objects.....	1-8
Associative and Navigational Interfaces .....	1-8
Metadata Class.....	1-9
Object Type Translator Utility.....	1-9
<b>Additional Support</b> .....	1-10
Building OCCI Demos.....	1-10
OCCI on the Oracle Technology Network .....	1-10

## 2 Installation and Upgrading

<b>Installing Oracle C++ Call Interface</b> .....	2-1
<b>Upgrading Considerations</b> .....	2-1
<b>Determining the Oracle Database Versions</b> .....	2-1
Determining the Oracle Client Version During Compilation .....	2-1
Determining the Oracle Client and Server Versions at Runtime .....	2-2
<b>Instant Client</b> .....	2-2
Benefits of Instant Client .....	2-2
Installing Instant Client.....	2-2
Oracle Technology Network .....	2-2
Instant Client SDK .....	2-3
Complete Client Installation.....	2-3
Oracle Universal Installer .....	2-3
Instant Client CD.....	2-4
Using Instant Client .....	2-4
Patching Instant Client Shared Libraries on Unix .....	2-4
Regenerating the Data Shared Library and Zip Files .....	2-4
Database Connection Names for Instant Client.....	2-5
Environment Variables for OCCI Instant Client .....	2-5
<b>Instant Client Light (English)</b> .....	2-6
Globalization Settings for Instant Client Light (English) .....	2-6
Using Instant Client Light (English).....	2-7
Installing Instant Client Light (English) .....	2-7
Oracle Technology Network Download.....	2-7
Client Admin Install .....	2-7
Oracle Universal Installer .....	2-7
<b>Using OCCI with Microsoft Visual C++</b> .....	2-8

## 3 Relational Programming

<b>Connecting to a Database</b> .....	3-1
Creating and Terminating an Environment.....	3-1
Opening and Closing a Connection .....	3-2
<b>Pooling Connections</b> .....	3-3
Using Connection Pools .....	3-3
Creating a Connection Pool.....	3-3
Proxy Connections .....	3-4
Stateless Connection Pooling.....	3-5
Database Resident Connection Pooling .....	3-8
Administrating Database Resident Connection Pools .....	3-9
Using Database Resident Connection Pools .....	3-10
<b>Executing SQL DDL and DML Statements</b> .....	3-11
Creating a Statement Object .....	3-11
Creating a Statement Object that Executes SQL Commands.....	3-12
Creating a Database Table .....	3-12
Inserting Values into a Database Table.....	3-12
Reusing the Statement Object.....	3-12
Terminating a Statement Object.....	3-13

<b>Types of SQL Statements in the OCCI Environment</b> .....	3-13
Standard Statements .....	3-13
Parameterized Statements.....	3-13
Callable Statements.....	3-14
Callable Statements that Use Array Parameters.....	3-14
Streamed Reads and Writes.....	3-15
Binding Data in Streaming Mode; SELECT/DML and PL/SQL.....	3-15
Fetching Data in Streaming Mode: PL/SQL.....	3-16
Fetching Data in Streaming Mode: ResultSet .....	3-17
Working with Multiple Streams .....	3-17
Modifying Rows Iteratively .....	3-18
Setting the Maximum Number of Iterations.....	3-18
Setting the Maximum Parameter Size.....	3-18
Executing an Iterative Operation.....	3-18
INotes on Iterative Execution.....	3-19
<b>Executing SQL Queries</b> .....	3-19
Using the Result Set .....	3-19
Specifying the Query .....	3-20
Optimizing Performance by Setting Prefetch Count .....	3-20
<b>Executing Statements Dynamically</b> .....	3-21
Statement Status Definitions .....	3-21
UNPREPARED.....	3-21
PREPARED .....	3-22
RESULT_SET_AVAILABLE.....	3-22
UPDATE_COUNT_AVAILABLE.....	3-22
NEEDS_STREAM_DATA.....	3-22
STREAM_DATA_AVAILABLE.....	3-23
<b>Committing a Transaction</b> .....	3-23
<b>Caching Statements</b> .....	3-23
<b>Handling Exceptions</b> .....	3-26
Handling Null and Truncated Data .....	3-27

## 4 Object Programming

<b>Overview of Object Programming</b> .....	4-1
<b>Working with Objects in OCCI</b> .....	4-2
Persistent Objects .....	4-2
Transient Objects.....	4-3
Values.....	4-4
<b>Representing Objects in C++ Applications</b> .....	4-4
Creating Persistent and Transient Objects .....	4-4
Creating Object Representations using the OTT Utility.....	4-5
<b>Developing an OCCI Object Application</b> .....	4-5
Basic Object Program Structure .....	4-5
Basic Object Operational Flow .....	4-6
Initialize OCCI in Object Mode.....	4-7
Pin Object .....	4-8
Operate on Object in Cache .....	4-8

Flush Changes to Object.....	4-8
Deletion of an Object .....	4-9
<b>Migrating C++ Applications Using OCCI.....</b>	<b>4-9</b>
Steps for Migration .....	4-9
<b>Overview of Associative Access .....</b>	<b>4-9</b>
Using SQL to Access Objects .....	4-10
Inserting and Modifying Values .....	4-10
<b>Overview of Navigational Access .....</b>	<b>4-10</b>
Retrieving an Object Reference (REF) from the Database Server .....	4-10
Pinning an Object .....	4-11
Manipulating Object Attributes .....	4-12
Marking Objects and Flushing Changes.....	4-12
Marking an Object as Modified (Dirty).....	4-12
Recording Changes in the Database .....	4-12
Garbage Collection in the Object Cache .....	4-12
Transactional Consistency of References.....	4-13
<b>Overview of Complex Object Retrieval.....</b>	<b>4-14</b>
Retrieving Complex Objects .....	4-14
Prefetching Complex Objects .....	4-16
<b>Working with Collections.....</b>	<b>4-16</b>
Fetching Embedded Objects .....	4-17
Nullness.....	4-17
<b>Using Object References.....</b>	<b>4-18</b>
<b>Deleting Objects from the Database .....</b>	<b>4-18</b>
<b>Type Inheritance .....</b>	<b>4-18</b>
Substitutability.....	4-19
NOT INSTANTIABLE Types and Methods.....	4-19
OCCI Support for Type Inheritance .....	4-20
Connection::getMetaData().....	4-20
Bind and Define Functions .....	4-20
OTT Support for Type Inheritance .....	4-20
<b>A Sample OCCI Application .....</b>	<b>4-21</b>

## 5 Data Types

<b>Overview of Oracle Data Types.....</b>	<b>5-1</b>
OCCI Type and Data Conversion.....	5-1
<b>Internal Data Types.....</b>	<b>5-2</b>
Character Strings and Byte Arrays .....	5-3
Universal Rowid (UROWID).....	5-3
<b>External Data Types .....</b>	<b>5-4</b>
Description of External Data Types.....	5-6
BFILE.....	5-6
BDOUBLE .....	5-6
BFLOAT.....	5-7
BLOB .....	5-7
CHAR.....	5-7
CHARZ.....	5-7

CLOB.....	5-7
DATE .....	5-7
Example 1, 01-JUN-2000, 3:17PM: .....	5-8
Example 2, 01-JAN-4712 BCE:.....	5-8
FLOAT .....	5-9
INTEGER.....	5-9
INTERVAL DAY TO SECOND .....	5-9
INTERVAL YEAR TO MONTH .....	5-10
LONG.....	5-10
LONG RAW.....	5-10
LONG VARCHAR.....	5-11
LONG VARRAW .....	5-11
NCLOB .....	5-11
NUMBER.....	5-11
OCCI BFILE .....	5-12
OCCI BLOB.....	5-12
OCCI BYTES .....	5-12
OCCI CLOB .....	5-12
OCCI DATE .....	5-12
OCCI NTERVALDS.....	5-12
OCCI INTERVALYM .....	5-12
OCCI NUMBER.....	5-12
OCCI POBJECT .....	5-12
OCCI REF .....	5-12
OCCI REFANY .....	5-12
OCCI STRING .....	5-13
OCCI TIMESTAMP .....	5-13
OCCI VECTOR.....	5-13
RAW.....	5-13
REF .....	5-13
ROWID .....	5-13
STRING.....	5-13
TIMESTAMP.....	5-13
TIMESTAMP WITH LOCAL TIME ZONE.....	5-14
TIMESTAMP WITH TIME ZONE.....	5-14
UNSIGNED INT.....	5-14
VARCHAR.....	5-14
VARCHAR2.....	5-15
VARNUM.....	5-15
VARRAW .....	5-15
NATIVE DOUBLE .....	5-15
NATIVE FLOAT.....	5-15
<b>Data Conversions</b> .....	5-16
Data Conversions for LOB Data Types.....	5-17
Data Conversions for Date, Timestamp, and Interval Data Types.....	5-17

## 6 Metadata

<b>Overview of Metadata</b> .....	6-1
Notes on Types and Attributes .....	6-1
<b>Describing Database Metadata</b> .....	6-2
Metadata Code Examples .....	6-2
<b>Attribute Reference</b> .....	6-5
Parameter Attributes .....	6-5
Table and View Attributes .....	6-6
Procedure, Function, and Subprogram Attributes .....	6-7
Package Attributes .....	6-7
Type Attributes .....	6-7
Type Attribute Attributes .....	6-9
Type Method Attributes .....	6-9
Collection Attributes .....	6-10
Synonym Attributes .....	6-11
Sequence Attributes .....	6-11
Column Attributes .....	6-11
Argument and Result Attributes .....	6-12
List Attributes .....	6-13
Schema Attributes .....	6-14
Database Attributes .....	6-14

## 7 Programming with LOBs

<b>Overview of LOBs</b> .....	7-1
Introducing Internal LOBs .....	7-1
Introducing External LOBs .....	7-2
Storing LOBs .....	7-2
<b>Creating LOBs in OCCI Applications</b> .....	7-2
<b>Restricting the Opening and Closing of LOBs</b> .....	7-3
<b>Reading and Writing LOBs</b> .....	7-4
Reading LOBs .....	7-4
Writing LOBs .....	7-5
Enhancing the Performance of LOB Reads and Writes .....	7-6
Using the getChunkSize() Method .....	7-7
Updating LOBs .....	7-7
Reading and Writing Multiple LOBs .....	7-7
Using the Interfaces for Reading and Writing Multiple LOBs .....	7-8
<b>Using Objects with LOB Attributes</b> .....	7-8
<b>Using SecureFiles</b> .....	7-9
Using SecureFile Compression .....	7-9
Using SecureFile Encryption .....	7-9
Using SecureFile Deduplication .....	7-10
Combining SecureFile Compression, Encryption, and Deduplication .....	7-10
SecureFile LOB Types and Constants .....	7-10



## 8 Object Type Translator Utility

<b>Overview of the Object Type Translator Utility</b> .....	8-1
<b>Using the OTT Utility</b> .....	8-2
<b>Creating Types in the Database</b> .....	8-2
<b>Invoking the OTT Utility</b> .....	8-2
Specifying OTT Parameters .....	8-3
Setting Parameters on the Command Line .....	8-3
Setting Parameters in the INTYPE File .....	8-3
Setting Parameters in the Configuration File.....	8-3
Invoking the OTT Utility on the Command Line.....	8-3
Elements Used on the OTT Command Line .....	8-4
OTT Utility Parameters .....	8-4
ATTRACCESS .....	8-5
CASE .....	8-5
CODE .....	8-6
CONFIG .....	8-6
CPPFILE .....	8-6
ERRTYPE.....	8-6
HFILE .....	8-7
INTYPE.....	8-7
MAPFILE.....	8-7
MAPFUNC.....	8-7
OUTTYPE.....	8-8
SCHEMA_NAMES .....	8-8
TRANSITIVE .....	8-9
UNICODE .....	8-9
USE_MARKER .....	8-11
USERID.....	8-11
Where OTT Parameters Can Appear .....	8-12
File Name Comparison Restriction .....	8-12
<b>Using the INTYPE File</b> .....	8-13
Overview of the INTYPE File.....	8-13
Structure of the INTYPE File .....	8-14
INTYPE File Type Specifications .....	8-14
Nested #include File Generation.....	8-15
<b>OTT Utility Data Type Mappings</b> .....	8-18
Default Name Mapping .....	8-22
<b>Overview of the OUTTYPE File</b> .....	8-23
<b>The OTT Utility and OCCI Applications</b> .....	8-24
C++ Classes Generated by the OTT Utility .....	8-26
Map Registry Function.....	8-26
Extending C++ Classes.....	8-27
<b>Carrying Forward User Added Code</b> .....	8-27
Properties of OTT Markers .....	8-28
Using OTT Markers .....	8-29

## 9 Globalization and Unicode Support

Overview of Globalization and Unicode Support.....	9-1
Specifying Charactersets.....	9-1
Data Types for Globalization and Unicode Support.....	9-2
UString Data Type .....	9-2
Multibyte and UTF16 data.....	9-3
CLOB and NCLOB Data Types.....	9-3
Objects and OTT Support .....	9-4

## 10 Oracle Streams Advanced Queuing

Overview of Oracle Streams Advanced Queuing.....	10-1
AQ Implementation in OCCI .....	10-2
Message .....	10-2
Agent.....	10-3
Producer .....	10-3
Consumer .....	10-3
Listener .....	10-3
Subscription .....	10-4
Creating Messages.....	10-4
Message Payloads .....	10-4
RAW.....	10-4
AnyData .....	10-4
User-defined .....	10-4
Message Properties .....	10-5
Correlation .....	10-5
Sender .....	10-5
Delay and Expiration.....	10-5
Recipients .....	10-5
Priority and Ordering.....	10-5
Enqueuing Messages .....	10-6
Dequeuing Messages.....	10-6
Dequeuing Options.....	10-7
Correlation .....	10-7
Mode .....	10-7
Navigation.....	10-7
Listening for Messages.....	10-7
Registering for Notification .....	10-8
Publish-Subscribe Notifications.....	10-8
Direct Registration .....	10-8
Open Registration .....	10-9
Notification Callback .....	10-11
Message Format Transformation .....	10-11

## 11 Oracle XA Library

Application Development with XA and OCCI .....	11-1
APIs for XA Support.....	11-2

## 12 Optimizing Performance of OCCI Applications

<b>Transparent Application Failover</b> .....	12-1
Using Transparent Application Failover .....	12-2
Objects and Transparent Application Failover .....	12-2
Connection Pooling and Transparent Application Failover .....	12-3
<b>Connection Sharing</b> .....	12-3
Introduction to Thread Safety .....	12-3
Implementing Thread Safety .....	12-4
Serialization.....	12-4
Automatic Serialization.....	12-4
Application-Provided Serialization.....	12-5
<b>Application Managed Data Buffering</b> .....	12-5
setDataBuffer() Method.....	12-6
executeArrayUpdate() Method .....	12-7
<b>Array Fetch Using next() Method</b> .....	12-8
<b>Modifying Rows Iteratively</b> .....	12-8
<b>Runtime Load Balancing of the Stateless Connection Pool</b> .....	12-9
API Support .....	12-9
<b>Fault Diagnosability</b> .....	12-9
ADR Base Location .....	12-9
Using ADRCI .....	12-11
Controlling ADR Creation and Disabling Fault Diagnosability .....	12-13

## 13 OCCI Application Programming Interface

<b>OCCI Classes and Methods</b> .....	13-2
Using OCCI Classes .....	13-3
OCCI Support for Windows NT and z/OS.....	13-4
Working with Collections of Refs.....	13-4
ResultSet Class .....	13-4
Statement Class .....	13-4
<b>Common OCCI Constants</b> .....	13-6
<b>Agent Class</b> .....	13-7
Agent() .....	13-7
getAddress().....	13-7
getName().....	13-8
getProtocol().....	13-8
isNull() .....	13-8
operator=() .....	13-8
setAddress() .....	13-8
setName() .....	13-9
setNull().....	13-9
setProtocol() .....	13-9
<b>AnyData Class</b> .....	13-10
AnyData() .....	13-12
getAsBDouble() .....	13-13
getAsBfile().....	13-13

getAsBFloat()	13-13
getAsBytes()	13-13
getAsDate()	13-13
getAsIntervalDS()	13-13
getAsIntervalYM()	13-14
getAsNumber()	13-14
getAsObject()	13-14
getAsRef()	13-14
getAsString()	13-14
getAsTimestamp()	13-14
getType()	13-14
isNull()	13-15
setFromBDouble()	13-15
setFromBfile()	13-15
setFromBFloat()	13-15
setFromBytes()	13-16
setFromDate()	13-16
setFromIntervalDS()	13-16
setFromIntervalYM()	13-16
setFromNumber()	13-17
setFromObject()	13-17
setFromRef()	13-17
setFromString()	13-17
setFromTimestamp()	13-18
setNull()	13-18
<b>BatchSQLException Class</b>	13-19
getException()	13-19
getFailedRowCount()	13-19
getRowNum()	13-19
<b>Bfile Class</b>	13-20
Bfile()	13-21
close()	13-21
closeStream()	13-21
fileExists()	13-21
getDirAlias()	13-22
getFileName()	13-22
getStream()	13-22
getUStringDirAlias()	13-22
getUStringFileName()	13-23
isInitialized()	13-23
isNull()	13-23
isOpen()	13-23
length()	13-23
open()	13-24
operator=()	13-24
operator==(())	13-24
operator!=(())	13-24

read() .....	13-25
setName() .....	13-25
setNull() .....	13-25
<b>Blob Class</b> .....	13-26
Blob() .....	13-27
append() .....	13-27
close() .....	13-27
closeStream() .....	13-28
copy() .....	13-28
getChunkSize() .....	13-28
getOptions() .....	13-29
getStream() .....	13-29
isInitialized() .....	13-29
isNull() .....	13-29
isOpen() .....	13-30
length() .....	13-30
open() .....	13-30
operator=() .....	13-30
operator==( ) .....	13-31
operator!= ( ) .....	13-31
read() .....	13-31
setEmpty() .....	13-32
setNull() .....	13-32
setOptions() .....	13-32
trim() .....	13-32
write() .....	13-33
writeChunk() .....	13-33
<b>Bytes Class</b> .....	13-34
Bytes() .....	13-34
byteAt() .....	13-34
getBytes() .....	13-35
isNull() .....	13-35
length() .....	13-35
operator=() .....	13-35
setNull() .....	13-36
<b>Clob Class</b> .....	13-37
Clob() .....	13-38
append() .....	13-38
close() .....	13-39
closeStream() .....	13-39
copy() .....	13-39
getCharSetForm() .....	13-40
getCharSetId() .....	13-40
getCharSetIdUString() .....	13-40
getChunkSize() .....	13-40
getOptions() .....	13-40
getStream() .....	13-41

isInitialized()	13-41
isNull()	13-41
isOpen()	13-41
length()	13-42
open()	13-42
operator=()	13-42
operator==(())	13-42
operator!=(())	13-43
read()	13-43
setCharSetId()	13-44
setCharSetIdUString()	13-44
setCharSetForm()	13-44
setEmpty()	13-44
setNull()	13-45
setOptions()	13-45
trim()	13-45
write()	13-46
writeChunk()	13-46
<b>Connection Class</b>	13-48
changePassword()	13-49
commit()	13-50
createStatement()	13-50
flushCache()	13-51
getClientCharSet()	13-51
getClientCharSetUString()	13-51
getClientNCHARCharSet()	13-51
getClientNCHARCharSetUString()	13-51
getClientVersion()	13-52
getMetaData()	13-52
getOCIServer()	13-53
getOCIServiceContext()	13-53
getOCISession()	13-53
getServerVersion()	13-53
getServerVersionUString()	13-53
getStmtCacheSize()	13-53
getTag()	13-54
isCached()	13-54
pinVectorOfRefs()	13-54
postToSubscriptions()	13-55
readVectorOfBfiles()	13-55
readVectorOfBlobs()	13-56
readVectorOfClobs()	13-56
registerSubscriptions()	13-57
rollback()	13-57
setCollectionAccessMode()	13-58
setStmtCacheSize()	13-58
setTAFNotify()	13-58

terminateStatement() .....	13-59
unregisterSubscription().....	13-59
writeVectorOfBlobs().....	13-60
writeVectorOfClobs() .....	13-60
<b>ConnectionPool Class</b> .....	13-62
createConnection() .....	13-62
createProxyConnection().....	13-63
getBusyConnections().....	13-63
getIncrConnections() .....	13-64
getMaxConnections().....	13-64
getMinConnections() .....	13-64
getOpenConnections().....	13-64
getPoolName().....	13-64
getStmtCacheSize() .....	13-64
getTimeout().....	13-65
setErrorOnBusy() .....	13-65
setPoolSize().....	13-65
setStmtCacheSize().....	13-65
setTimeout() .....	13-66
terminateConnection().....	13-66
<b>Consumer Class</b> .....	13-67
Consumer().....	13-68
getConsumerName() .....	13-69
getCorrelationId().....	13-69
getDequeueMode() .....	13-69
getMessageIdToDequeue() .....	13-69
getPositionOfMessage() .....	13-69
getQueueName().....	13-70
getTransformation().....	13-70
getVisibility() .....	13-70
getWaitTime().....	13-70
isNull() .....	13-70
operator=() .....	13-70
receive() .....	13-71
setAgent() .....	13-71
setConsumerName().....	13-71
setCorrelationId() .....	13-72
setDequeueMode().....	13-72
setMessageIdToDequeue().....	13-72
setNull() .....	13-72
setPositionOfMessage().....	13-73
setQueueName().....	13-73
setTransformation() .....	13-73
setVisibility().....	13-73
setWaitTime().....	13-74
<b>Date Class</b> .....	13-75
Date().....	13-76

addDays()	13-77
addMonths()	13-77
daysBetween()	13-77
fromBytes()	13-77
fromText()	13-78
getDate()	13-78
getSystemDate()	13-79
isNull()	13-79
lastDay()	13-79
nextDay()	13-79
operator=()	13-80
operator==(())	13-80
operator!=(())	13-80
operator>()	13-81
operator>=()	13-81
operator<()	13-81
operator<=()	13-82
setDate()	13-82
setNull()	13-82
toBytes()	13-83
toText()	13-83
toZone()	13-83
<b>Environment Class</b>	13-85
createConnection()	13-86
createConnectionPool()	13-87
createEnvironment()	13-88
createStatelessConnectionPool()	13-89
enableSubscription()	13-90
disableSubscription()	13-90
getCacheMaxSize()	13-90
getCacheOptSize()	13-90
getCacheSortedFlush()	13-91
getCurrentHeapSize()	13-91
getLDAPAdminContext()	13-91
getLDAPAuthentication()	13-91
getLDAPHost()	13-91
getLDAPPort()	13-91
getMap()	13-91
getOCIEnvironment()	13-92
getXAConnection()	13-92
getXAEnvironment()	13-92
releaseXAConnection()	13-92
releaseXAEnvironment()	13-93
setCacheMaxSize()	13-93
setCacheOptSize()	13-93
setCacheSortedFlush()	13-93
setLDAPAdminContext()	13-94



setLDAPAuthentication() .....	13-94
setLDAPHostAndPort() .....	13-94
setLDAPLoginNameAndPassword().....	13-95
terminateConnection().....	13-95
terminateConnectionPool().....	13-95
terminateEnvironment().....	13-95
terminateStatelessConnectionPool().....	13-96
<b>IntervalDS Class</b> .....	13-97
IntervalDS() .....	13-99
fromText().....	13-99
fromUText().....	13-100
getDay() .....	13-100
getFracSec() .....	13-100
getHour() .....	13-100
getMinute().....	13-100
getSecond().....	13-101
isNull() .....	13-101
operator*() .....	13-101
operator*=() .....	13-101
operator=() .....	13-101
operator==(()).....	13-102
operator!=(()) .....	13-102
operator/() .....	13-102
operator/=(()).....	13-103
operator>() .....	13-103
operator>=() .....	13-103
operator<() .....	13-103
operator<=() .....	13-104
operator-().....	13-104
operator-=(()) .....	13-104
operator+() .....	13-105
operator+=(()) .....	13-105
set() .....	13-105
setNull() .....	13-106
toText().....	13-106
toUText().....	13-106
<b>IntervalYM Class</b> .....	13-107
IntervalYM().....	13-108
fromText().....	13-109
fromUText().....	13-109
getMonth().....	13-110
getYear() .....	13-110
isNull() .....	13-110
operator*() .....	13-110
operator*=().....	13-110
operator=() .....	13-111
operator==(()).....	13-111

operator!=(())	13-111
operator/()	13-111
operator/=(())	13-112
operator>()	13-112
operator>=()	13-112
operator<()	13-113
operator<=()	13-113
operator-()	13-113
operator-=(())	13-114
operator+()	13-114
operator+=(())	13-114
set()	13-114
setNull()	13-115
toText()	13-115
toUText()	13-115
<b>Listener Class</b>	13-116
Listener()	13-116
getAgentList()	13-116
getTimeOutForListen()	13-117
listen()	13-117
setAgentList()	13-117
setTimeOutForListen()	13-117
<b>Map Class</b>	13-118
put()	13-118
<b>Message Class</b>	13-119
Message()	13-120
getAnyData()	13-120
getAttemptsToDequeue()	13-121
getBytes()	13-121
getCorrelationId()	13-121
getDelay()	13-121
getExceptionQueueName()	13-121
getExpiration()	13-121
getMessageEnqueuedTime()	13-122
getMessageState()	13-122
getObject()	13-122
getOriginalMessageId()	13-122
getPayloadType()	13-122
getPriority()	13-122
getSenderId()	13-123
isNull()	13-123
operator=()	13-123
setAnyData()	13-123
setBytes()	13-123
setCorrelationId()	13-124
setDelay()	13-124
setExceptionQueueName()	13-124

setExpiration() .....	13-125
setNull() .....	13-125
setObject() .....	13-125
setOriginalMessageId() .....	13-125
setPriority() .....	13-126
setRecipientList() .....	13-126
setSenderId() .....	13-126
<b>MetaData Class</b> .....	13-127
MetaData() .....	13-136
getAttributeCount() .....	13-136
getAttributeId() .....	13-136
getAttributeType() .....	13-136
getBoolean() .....	13-137
getInt() .....	13-137
getMetaData() .....	13-137
getNumber() .....	13-138
getRef() .....	13-138
getString() .....	13-138
getTimeStamp() .....	13-138
getUInt() .....	13-139
getUString() .....	13-139
getVector() .....	13-139
operator=() .....	13-139
<b>NotifyResult Class</b> .....	13-141
getConsumerName() .....	13-141
getMessage() .....	13-141
getMessageId() .....	13-141
getPayload() .....	13-141
getQueueName() .....	13-141
<b>Number Class</b> .....	13-142
Number() .....	13-145
abs() .....	13-146
arcCos() .....	13-146
arcSin() .....	13-146
arcTan() .....	13-146
arcTan2() .....	13-147
ceil() .....	13-147
cos() .....	13-147
exp() .....	13-147
floor() .....	13-147
fromBytes() .....	13-147
fromText() .....	13-148
hypCos() .....	13-148
hypSin() .....	13-149
hypTan() .....	13-149
intPower() .....	13-149
isNull() .....	13-149

ln()	13-149
log()	13-149
operator++()	13-150
operator--()	13-150
operator*()	13-150
operator/()	13-151
operator%()	13-151
operator+()	13-151
operator-()	13-151
operator-()	13-152
operator<()	13-152
operator<=()	13-152
operator>()	13-153
operator>=()	13-153
operator==(())	13-153
operator!=(())	13-154
operator=()	13-154
operator*=(())	13-154
operator/=(())	13-154
operator%=(())	13-155
operator+=(())	13-155
operator-=(())	13-155
operator char()	13-155
operator signed char()	13-156
operator double()	13-156
operator float()	13-156
operator int()	13-156
operator long()	13-156
operator long double()	13-156
operator short()	13-157
operator unsigned char()	13-157
operator unsigned int()	13-157
operator unsigned long()	13-157
operator unsigned short()	13-157
power()	13-157
prec()	13-158
round()	13-158
setNull()	13-158
shift()	13-158
sign()	13-159
sin()	13-159
squareroot()	13-159
tan()	13-159
toBytes()	13-159
toText()	13-159
trunc()	13-160
<b>PObject Class</b>	<b>13-161</b>

PObject()	13-162
flush()	13-162
getConnection()	13-162
getRef()	13-162
getSQLTypeName()	13-163
isLocked()	13-163
isNull()	13-163
lock()	13-163
markDelete()	13-163
markModified()	13-163
operator=()	13-164
operator delete()	13-164
operator new()	13-164
pin()	13-165
setNull()	13-165
unmark()	13-165
unpin()	13-165
<b>Producer Class</b>	13-167
Producer()	13-168
getQueueName()	13-168
getRelativeMessageId()	13-168
getSequenceDeviation()	13-168
getTransformation()	13-168
getVisibility()	13-169
isNull()	13-169
operator=()	13-169
send()	13-169
setNull()	13-170
setQueueName()	13-170
setRelativeMessageId()	13-170
setSequenceDeviation()	13-170
setTransformation()	13-171
setVisibility()	13-171
<b>Ref Class</b>	13-172
Ref()	13-173
clear()	13-173
getConnection()	13-173
isClear()	13-173
isNull()	13-173
markDelete()	13-174
operator->()	13-174
operator*()	13-174
operator==(())	13-174
operator!=(())	13-175
operator=(())	13-175
ptr()	13-175
setLock()	13-175

setNull() .....	13-176
setPrefetch().....	13-176
unmarkDelete().....	13-176
<b>RefAny Class</b> .....	13-177
RefAny() .....	13-177
clear().....	13-178
getConnection() .....	13-178
isNull() .....	13-178
markDelete() .....	13-178
operator=() .....	13-178
operator==( ).....	13-178
operator!=( ) .....	13-179
unmarkDelete().....	13-179
<b>ResultSet Class</b> .....	13-180
cancel() .....	13-182
closeStream().....	13-182
getBDouble() .....	13-183
getBfile().....	13-183
getBFloat() .....	13-183
getBlob() .....	13-183
getBytes() .....	13-184
getCharSet().....	13-184
getCharSetUString().....	13-184
getClob() .....	13-184
getColumnListMetaData() .....	13-185
getCurrentStreamColumn().....	13-185
getCurrentStreamRow() .....	13-185
getCursor() .....	13-185
getDatabaseNCHARParam() .....	13-186
getDate() .....	13-186
getDouble() .....	13-186
getFloat() .....	13-187
getInt() .....	13-187
getIntervalDS() .....	13-187
getIntervalYM() .....	13-187
getMaxColumnSize() .....	13-188
getNumArrayRows() .....	13-188
getNumber() .....	13-188
getObject() .....	13-188
getRef().....	13-189
getRowid() .....	13-189
getRowPosition() .....	13-189
getStatement().....	13-189
getStream() .....	13-189
getString() .....	13-190
getTimestamp().....	13-190
getUInt() .....	13-190

getUString()	13-190
getVector()	13-191
getVectorOfRefs()	13-193
isNull()	13-193
isTruncated()	13-193
next()	13-194
preTruncationLength()	13-194
setBinaryStreamMode()	13-194
setCharacterStreamMode()	13-195
setCharSet()	13-195
setCharSetUString()	13-195
setDatabaseNCHARParam()	13-196
setDataBuffer()	13-196
setErrorOnNull()	13-197
setErrorOnTruncate()	13-197
setMaxColumnSize()	13-197
status()	13-198
<b>SQLException Class</b>	13-199
SQLException()	13-199
getErrorCode()	13-199
getMessage()	13-200
getNLSMessage()	13-200
getNLSUStringMessage()	13-200
getUStringMessage()	13-200
getXAErrorCode()	13-201
setErrorCtx()	13-201
what()	13-201
<b>StatelessConnectionPool Class</b>	13-202
getAnyTaggedConnection()	13-203
getAnyTaggedProxyConnection()	13-204
getBusyConnections()	13-205
getBusyOption()	13-205
getConnection()	13-205
getIncrConnections()	13-206
getMaxConnections()	13-207
getMinConnections()	13-207
getOpenConnections()	13-207
getPoolName()	13-207
getProxyConnection()	13-207
getStmtCacheSize()	13-209
getTimeout()	13-209
releaseConnection()	13-209
setBusyOption()	13-209
setPoolSize()	13-210
setTimeout()	13-210
setStmtCacheSize()	13-210
terminateConnection()	13-211

<b>Statement Class</b> .....	13-212
addIteration() .....	13-216
closeResultSet() .....	13-216
closeStream() .....	13-216
disableCaching() .....	13-216
execute().....	13-217
executeArrayUpdate() .....	13-217
executeQuery() .....	13-218
executeUpdate() .....	13-218
getAutoCommit() .....	13-218
getBatchErrorMode().....	13-218
getBDouble() .....	13-219
getBfile() .....	13-219
getBFloat() .....	13-219
getBlob() .....	13-219
getBytes() .....	13-220
getCharSet().....	13-220
getCharSetUString().....	13-220
getClob() .....	13-220
getConnection() .....	13-221
getCurrentIteration() .....	13-221
getCurrentStreamIteration() .....	13-221
getCurrentStreamParam().....	13-221
getCursor() .....	13-221
getDatabaseNCHARParam().....	13-222
getDate() .....	13-222
getDouble() .....	13-222
getFloat() .....	13-223
getInt() .....	13-223
getIntervalDS() .....	13-223
getIntervalYM() .....	13-223
getMaxIterations() .....	13-224
getMaxParamSize() .....	13-224
getNumber() .....	13-224
getObject() .....	13-224
getOCIStatement() .....	13-225
getRef() .....	13-225
getResultSet() .....	13-225
getRowid().....	13-225
getSQL().....	13-225
getSQLUString() .....	13-226
getStream() .....	13-226
getString().....	13-226
getTimestamp().....	13-226
getUInt() .....	13-227
getUpdateCount() .....	13-227
getUString().....	13-227



getVector()	13-227
getVectorOfRefs()	13-229
isNull()	13-230
isTruncated()	13-230
preTruncationLength()	13-230
registerOutParam()	13-231
setAutoCommit()	13-232
setBatchErrorMode()	13-232
setBDouble()	13-232
setBfile()	13-232
setBFloat()	13-233
setBinaryStreamMode()	13-233
setBlob()	13-233
setBytes()	13-234
setCharacterStreamMode()	13-234
setCharSet()	13-234
setCharSetUString()	13-235
setClob()	13-235
setDate()	13-235
setDatabaseNCHARParam()	13-236
setDataBuffer()	13-236
setDataBufferArray()	13-237
setDouble()	13-238
setErrorOnNull()	13-238
setErrorOnTruncate()	13-239
setFloat()	13-239
setInt()	13-239
setIntervalDS()	13-240
setIntervalYM()	13-240
setMaxIterations()	13-240
setMaxParamSize()	13-241
setNull()	13-241
setNumber()	13-242
setObject()	13-242
setPrefetchMemorySize()	13-242
setPrefetchRowCount()	13-243
setRef()	13-243
setRowid()	13-243
setSQL()	13-244
setSQLUString()	13-244
setString()	13-244
setTimestamp()	13-245
setUInt()	13-245
setUString()	13-245
setVector()	13-246
setVectorOfRefs()	13-251
status()	13-252

<b>Stream Class</b> .....	13-253
readBuffer() .....	13-253
readLastBuffer() .....	13-254
writeBuffer() .....	13-254
writeLastBuffer() .....	13-254
status() .....	13-254
<b>Subscription Class</b> .....	13-256
Subscription() .....	13-257
getCallbackContext() .....	13-258
getDatabaseServersCount() .....	13-258
getDatabaseServerNames() .....	13-258
getNotifyCallback() .....	13-258
getPayload() .....	13-258
getSubscriptionName() .....	13-259
getSubscriptionNamespace() .....	13-259
getRecipientName() .....	13-259
getPresentation() .....	13-259
getProtocol() .....	13-259
isNull() .....	13-259
operator=() .....	13-260
setCallbackContext() .....	13-260
setDatabaseServerNames() .....	13-260
setNotifyCallback() .....	13-260
setNull() .....	13-261
setPayload() .....	13-261
setPresentation() .....	13-261
setProtocol() .....	13-261
setSubscriptionName() .....	13-262
setSubscriptionNamespace() .....	13-262
setRecipientName() .....	13-262
<b>Timestamp Class</b> .....	13-263
Timestamp() .....	13-264
fromText() .....	13-266
getDate() .....	13-267
getTime() .....	13-267
getTimeZoneOffset() .....	13-268
intervalAdd() .....	13-268
intervalSub() .....	13-268
isNull() .....	13-269
operator=() .....	13-269
operator==( ) .....	13-269
operator!=( ) .....	13-269
operator>( ) .....	13-270
operator>=( ) .....	13-270
operator<( ) .....	13-270
operator<=( ) .....	13-271
setDate() .....	13-271

setNull() ..... 13-271  
setTime() ..... 13-271  
setTimeZoneOffset() ..... 13-272  
subDS() ..... 13-272  
subYM() ..... 13-272  
toText()..... 13-273

**Index**

## List of Examples

1-1	Creating a Table .....	1-4
1-2	Specifying Access to a Table.....	1-4
1-3	Creating an Object Table.....	1-4
1-4	Inserting Data Through Input Bind Variables.....	1-5
1-5	Inserting Objects into the Oracle Database .....	1-5
1-6	Using the Simple SELECT Statement.....	1-5
1-7	Using the SELECT Statement with Input Variables .....	1-5
1-8	Using PL/SQL to Obtain an Output Variable .....	1-6
1-9	Using PL/SQL to Insert Partial Records into Placeholders.....	1-6
1-10	Using SQL to Extract Partial Records .....	1-7
2-1	How to Determine the Major Client Version and Set Performance Features .....	2-1
2-2	Installing Instant Client Light (English) through Oracle Universal Installer.....	2-8
3-1	How to Create an OCCI Environment.....	3-1
3-2	How to Terminate an OCCI Environment .....	3-1
3-3	How to Use Environment Scope with Blob Objects.....	3-2
3-4	How to Create an Environment and then a Connection to the Database.....	3-2
3-5	How to Terminate a Connection to the Database and the Environment.....	3-3
3-6	The createConnectionPool() Method .....	3-3
3-7	How to Create a Connection Pool .....	3-4
3-8	The createProxyConnection() Method.....	3-4
3-9	How to Use a StatelessConnectionPool.....	3-6
3-10	How to Create and Use a Homogeneous Stateless Connection Pool.....	3-6
3-11	How to Create and Use a Heterogeneous Stateless Connection Pool.....	3-7
3-12	How to Administer the Database Resident Connection Pools.....	3-9
3-13	How to Get a Connection from a Database Resident Connection Pool.....	3-10
3-14	Using Client-Side Pool and Server-Side Pool .....	3-11
3-15	How to Create a Statement.....	3-11
3-16	How to Create a Database Table Using the executeUpdate() Method .....	3-12
3-17	How to Add Records Using the executeUpdate() Method.....	3-12
3-18	How to Specify a SQL Statement Using the setSQL() Method.....	3-12
3-19	How to Reset a SQL Statement Using the setSQL() Method .....	3-12
3-20	How to Terminate a Statement Using the terminateStatement() Method.....	3-13
3-21	How to Use setxxx() Methods to Set Individual Column Values.....	3-14
3-22	How to Specify the IN Parameters of a PL/SQL Stored Procedure .....	3-14
3-23	How to Specify OUT Parameters of a PL/SQL Stored Procedure .....	3-14
3-24	How to Bind Data in a Streaming Mode .....	3-16
3-25	How to Fetch Data in a Streaming Mode Using PL/SQL.....	3-16
3-26	How to Read and Write with Multiple Streams.....	3-17
3-27	How to Fetch Data in Streaming Mode Using ResultSet .....	3-20
3-28	Statement Caching without Connection Pooling .....	3-24
3-29	Statement Caching with Connection Pooling.....	3-24
4-1	Creating Standalone Objects .....	4-3
4-2	Creating Embedded Objects.....	4-3
4-3	Two methods for operator new in the Object Type Translator Utility .....	4-3
4-4	How to Dynamically Create a Transient Object.....	4-4
4-5	How to Create a Transient Object as a Local Variable .....	4-4
4-6	Creating a Persistent Object.....	4-4
4-7	Creating a Transient Object .....	4-5
4-8	OTT Support Inheritance .....	4-20
4-9	Listing of demo2.sql for a Sample OCCI Application .....	4-21
4-10	Listing of demo2.typ for a Sample OCCI Application .....	4-21
4-11	Listing of OTT Command that Generates Files for a Sample OCCI Application.....	4-22
4-12	Listing of mappings.h for a Sample OCCI Application .....	4-22
4-13	Listing of mappings.cpp for a Sample OCCI Application.....	4-22

4-14	Listing of demo2.h for a Sample OCCI Application.....	4-22
4-15	Listing of demo2.cpp for a Sample OCCI Application.....	4-25
4-16	Listing of myDemo.h for a Sample OCCI Application .....	4-34
4-17	Listing for myDemo.cpp for a Sample OCCI Application.....	4-35
4-18	Listing of main.cpp for a Sample OCCI Application.....	4-37
5-1	Definition of the BDOUBLE Data Type.....	5-6
5-2	Definition of the BFLOAT Data Type .....	5-7
6-1	How to Obtain Metadata About Attributes of a Simple Database Table .....	6-2
6-2	How to Obtain Metadata from a Column Containing User-Defined Types.....	6-3
6-3	How to Obtain Object Metadata from a Reference .....	6-4
6-4	How to Obtain Metadata About a Select List from a ResultSet Object.....	6-5
7-1	How to Read Non-Streamed BLOBs.....	7-4
7-2	How to Read Non-Streamed BFILEs .....	7-4
7-3	How to Read Streamed BLOBs .....	7-5
7-4	How to Write Non-Streamed BLOBs .....	7-5
7-5	How to Write Streamed BLOBs .....	7-6
7-6	Updating a CLOB Value .....	7-7
7-7	Updating a BFILE Value .....	7-7
7-8	How to Use a Persistent Object with a BLOB Attribute.....	7-8
7-9	How to Use a Persistent Object with a BFILE Attribute .....	7-9
8-1	How to Use the OTT Utility .....	8-2
8-2	Object Creation Statements of the OTT Utility.....	8-2
8-3	How to Invoke the OTT Utility to Generate C++ Classes.....	8-4
8-4	How to use the SCHEMA_NAMES Parameter in OTT Utility .....	8-8
8-5	How to Define a Schema for Unicode Support in OTT.....	8-10
8-6	How to Use UNICODE=ALL Parameter in OTT.....	8-10
8-7	How to Use UNICODE=ONLYCHAR Parameter in OTT .....	8-11
8-8	How to Create a User Defined INTYPE File Using the OTT Utility .....	8-13
8-9	Listing of ott95a.h.....	8-16
8-10	Listing of ott95b.h .....	8-17
8-11	How to Represent Object Attributes Using the OTT Utility.....	8-18
8-12	How to Map Object Data Types Using the OTT Utility .....	8-20
8-13	OUTTYPE File Generated by the OTT Utility .....	8-23
8-14	How to Generate C++ Classes Using the OTT Utility.....	8-26
8-15	How to Extend C++ Classes Using the OTT Utility .....	8-27
8-16	How to Add User Code to a Header File Using OTT Utility .....	8-29
8-17	How to Add User Code to the Source File Using the OTT Utility .....	8-30
9-1	How to Use Globalization and Unicode Support .....	9-1
9-2	Using wstring Data Type.....	9-2
9-3	Binding UTF8 Data Using the string Data Type .....	9-3
9-4	Binding UTF16 Data Using the UString Data Type.....	9-3
9-5	Using CLOB and NCLOB Data Types .....	9-3
10-1	Creating an Agent.....	10-3
10-2	Setting the Agent on the Consumer .....	10-3
10-3	Creating an AnyData Message with a String Payload .....	10-4
10-4	Determining the Type of the Payload in an AnyData Message.....	10-4
10-5	Creating an User-defined Payload .....	10-4
10-6	Specifying the Correlation identifier.....	10-5
10-7	Specifying the Sender identifier.....	10-5
10-8	Specifying the Delay and Expiration times of the message.....	10-5
10-9	Specifying message recipients.....	10-5
10-10	Specifying the Priority of a Message.....	10-5
10-11	Creating a Producer, Setting Visibility, and Enqueuing the Message .....	10-6
10-12	Creating a Consumer, Naming the Consumer, and Receiving a Message.....	10-6
10-13	Receiving a Message.....	10-6

10-14	Specifying dequeuing options.....	10-7
10-15	Listening for messages .....	10-7
10-16	How to Register for Notifications; Direct Registration .....	10-8
10-17	How to Use Open Registration with LDAP .....	10-10
11-1	How to Use Transaction Managers with XA .....	11-1
12-1	How to Insert Records Using the addIteration() method .....	12-7
12-2	How to Insert Records Using the executeArrayUpdate() Method .....	12-7
12-3	How to use Array Fetch with a ResultSet .....	12-8
12-4	How to Modify Rows Iteratively and Handle Errors .....	12-8
12-5	How to Use ADRCI for OCCI Application Incidents .....	12-12
12-6	How to Use ADRCI for Instant Client .....	12-13
13-1	Converting From an SQL Pre-Defined Type To AnyData Type.....	13-10
13-2	Creating an SQL Pre-Defined Type From AnyData Type .....	13-10
13-3	Converting From a User-Defined Type To AnyData Type .....	13-10
13-4	Converting From a User-Defined Type To AnyData Type .....	13-11
13-5	How to Get a Date from Database and Use it in Standalone Calculations .....	13-75
13-6	How to Use an Empty IntervalDS Object through Direct Assignment .....	13-97
13-7	How to Use an Empty IntervalDS Object Through *Text() Methods.....	13-97
13-8	How to Use an Empty IntervalYM Object Through Direct Assignment.....	13-107
13-9	How to Use an IntervalYM Object Through ResultSet and toText() Method.....	13-107
13-10	How to Retrieve and Use a Number Object.....	13-142
13-11	Using Default Timestamp Constructor.....	13-265
13-12	Using fromText() method to Initialize a NULL Timestamp Instance .....	13-266
13-13	Comparing Timestamps Stored in the Database.....	13-266

## List of Figures

1-1	The OCCI Development Process .....	1-2
4-1	Basic Object Operational Flow .....	4-7
8-1	The OTT Utility with OCCI.....	8-25

## List of Tables

3-1	Normal Data - Not Null and Not Truncated .....	3-27
3-2	Null Data .....	3-27
3-3	Truncated Data .....	3-28
5-1	Summary of Oracle Internal Data Types .....	5-2
5-2	External Data Types and Corresponding C++ and OCCI Types.....	5-4
5-3	Format of the DATE Data Type .....	5-8
5-4	VARNUM Examples .....	5-15
5-5	Data Conversions Between External and Internal Data Types .....	5-16
5-6	Data Conversions for LOBs .....	5-17
5-7	Data Conversions for Date, Timestamp, and Interval Data Types.....	5-18
6-1	Attributes that Belong to All Elements .....	6-5
6-2	Attributes that Belong to Tables or Views.....	6-6
6-3	Attributes Specific to Tables .....	6-6
6-4	Attributes that Belong to Procedures or Functions.....	6-7
6-5	Attributes that Belong to Package Subprograms .....	6-7
6-6	Attributes that Belong to Packages.....	6-7
6-7	Attributes that Belong to Types .....	6-7
6-8	Attributes that Belong to Type Attributes.....	6-9
6-9	Attributes that Belong to Type Methods .....	6-9
6-10	Attributes that Belong to Collection Types .....	6-10
6-11	Attributes that Belong to Synonyms .....	6-11
6-12	Attributes that Belong to Sequences .....	6-11
6-13	Attributes that Belong to Columns of Tables or Views .....	6-12
6-14	Attributes that Belong to Arguments / Results .....	6-12
6-15	Values for ATTR_LIST_TYPE .....	6-13
6-16	Attributes Specific to Schemas .....	6-14
6-17	Attributes Specific to Databases .....	6-14
7-1	Values of Type LobOptionType.....	7-10
7-2	Values of Type LobOptionValue .....	7-10
8-1	Summary of OTT Utility Parameters .....	8-5
8-2	C++ Object Data Type Mappings for Object Type Attributes.....	8-19
10-1	Notification Result Attributes; ANONYMOUS and AQ Namespace.....	10-11
13-1	Summary of OCCI Classes .....	13-2
13-2	Enumerated Values Used by All OCCI Classes .....	13-6
13-3	Summary of Agent Methods .....	13-7
13-4	OCCI Data Types supported by AnyData Class .....	13-11
13-5	Summary of AnyData Methods.....	13-12
13-6	Summary of BatchSQLException Methods.....	13-19
13-7	Summary of Bfile Methods.....	13-20
13-8	Summary of Blob Methods.....	13-26
13-9	Summary of Bytes Methods .....	13-34
13-10	Summary of Clob Methods.....	13-37
13-11	Enumerated Values Used by Connection Class .....	13-48
13-12	Summary of Connection Methods.....	13-48
13-13	Summary of ConnectionPool Methods.....	13-62
13-14	Enumerated Values Used by Consumer Class .....	13-67
13-15	Summary of Consumer Methods .....	13-67
13-16	Summary of Date Methods.....	13-75
13-17	Enumerated Values Used by Environment Class .....	13-85
13-18	Summary of Environment Methods.....	13-85
13-19	Fields of IntervalDS Class.....	13-97
13-20	Summary of IntervalDS Methods.....	13-98
13-21	Fields of IntervalYM Class.....	13-107



13-22	Summary of IntervalYM Methods.....	13-108
13-23	Summary of Listener Methods.....	13-116
13-24	Enumerated Values Used by Message Class .....	13-119
13-25	Summary of Message Methods.....	13-119
13-26	Enumerated Values Used by MetaData Class .....	13-127
13-27	Summary of MetaData Methods.....	13-135
13-28	Summary of NotifyResult Methods .....	13-141
13-29	Summary of Number Methods .....	13-143
13-30	Enumerated Values Used by PObject Class.....	13-161
13-31	Summary of PObject Methods .....	13-161
13-32	Enumerated Values Used by Producer Class .....	13-167
13-33	Summary of Producer Methods.....	13-167
13-34	Enumerated Values Used by Ref Class.....	13-172
13-35	Summary of Ref Methods .....	13-172
13-36	Summary of RefAny Methods .....	13-177
13-37	Enumerated Values Used by ResultSet Class .....	13-180
13-38	Summary of ResultSet Methods .....	13-180
13-39	Summary of SQLException .....	13-199
13-40	Enumerated Values Used by StatelessConnectionPool Class .....	13-202
13-41	Summary of StatelessConnectionPool Methods.....	13-202
13-42	Enumerated Values used by the Statement Class .....	13-212
13-43	Statement Methods .....	13-212
13-44	Enumerated Values Used by Stream Class .....	13-253
13-45	Summary of Stream Methods .....	13-253
13-46	Enumerated Values Used by Subscription Class .....	13-256
13-47	Summary of Subscription Methods.....	13-256
13-48	Fields of Timestamp and Their Legal Ranges.....	13-263
13-49	Summary of Timestamp Methods.....	13-263



---

---

# Preface

The Oracle C++ Call Interface (OCI) is an application programming interface (API) that allows applications written in C++ to interact with one or more Oracle database servers. OCI gives your programs the ability to perform the full range of database operations that are possible with an Oracle database server, including SQL statement processing and object manipulation.

## Audience

The *Oracle C++ Call Interface Programmer's Guide* is intended for programmers, system analysts, project managers, and other Oracle users who perform, or are interested in learning about, the following tasks:

- Design and develop database applications in the Oracle environment.
- Convert existing database applications to run in the Oracle environment.
- Manage the development of database applications.

To use this document, you need a basic understanding of object-oriented programming concepts, familiarity with the use of Structured Query Language (SQL), and a working knowledge of application development using C++.

## Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc>.

### Access to Oracle Support

Oracle customers have access to electronic support through My Oracle Support. For information, visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info> or visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs> if you are hearing impaired.

## Related Documents

For more information, see these Oracle resources:

- Oracle C++ Call Interface product information page for white papers, additional examples, and so on, at <http://www.oracle.com/technology/tech/oci/occi/>
- Discussion forum for all Oracle C++ Call Interface related information is at <http://forums.oracle.com/forums/forum.jspa?forumID=168>
- Demos at `$ORACLE_HOME/rdbms/demo`
- *Oracle Database Concepts*
- *Oracle Database SQL Language Reference*
- *Oracle Database Object-Relational Developer's Guide*
- *Oracle Database SecureFiles and Large Objects Developer's Guide*
- *Oracle Database New Features Guide*
- *Oracle Call Interface Programmer's Guide*
- *Oracle Database Administrator's Guide*
- *Oracle Streams Advanced Queuing User's Guide*
- *Oracle Database Globalization Support Guide*
- Many of the examples in this book use the sample schemas of the seed database, which is installed by default when you install Oracle. Refer to *Oracle Database Sample Schemas* for information on how these schemas were created and how you can use them yourself.

## Conventions

The following text conventions are used in this document:

Convention	Meaning
<b>boldface</b>	Boldface type indicates graphical user interface elements associated with an action, or terms defined in text or the glossary.
<i>italic</i>	Italic type indicates book titles, emphasis, or placeholder variables for which you supply particular values.
<code>monospace</code>	Monospace type indicates commands within a paragraph, URLs, code in examples, text that appears on the screen, or text that you enter.

---

---

# What's New in Oracle C++ Call Interface?

This section describes new features in *Oracle C++ Call Interface Programmer's Guide* and supplies pointers to additional information.

## New Features for Oracle Database 11g Release 1 (11.1)

The following OCCI features are new to the Oracle Database 11g Release 1:

### Database Resident Connection Pooling

This feature is described in "[Database Resident Connection Pooling](#)" on page 3-8.

"[Administering Database Resident Connection Pools](#)" on page 3-9 describes the responsibilities of a SYSDBA user in activating and maintaining this feature, while "[Using Database Resident Connection Pools](#)" on page 3-10 discusses the programmatic steps.

This feature adds new versions of this method to [Environment Class](#):

- [createConnection\(\)](#) on page 13-86, two new versions

This feature adds new versions of these methods to [StatelessConnectionPool Class](#):

- [getConnection\(\)](#) on page 13-205, six new versions
- [getProxyConnection\(\)](#) on page 13-207, four new versions

### SecureFile Compression, Encryption, and Deduplication

This feature is thoroughly described in the *Oracle Database SecureFiles and Large Objects Developer's Guide*. Information specific to OCCI is in section "[Using SecureFiles](#)" on page 7-9 of [Chapter 7, "Programming with LOBs"](#). Section "[SecureFile LOB Types and Constants](#)" on page 7-10 describes the new LOB attributes, while [Chapter 13, "OCCI Application Programming Interface"](#) documents the new and changed APIs for the OCCI interface.

Section "[SecureFile LOB Types and Constants](#)" lists two new attribute types for LOBs, and adds more options to an existing type. These are all listed in the following tables:

- [Table 7-1, "Values of Type LobOptionType"](#) on page 7-10
- [Table 7-2, "Values of Type LobOptionValue"](#) on page 7-10

The following new methods are added to the [Blob Class](#):

- [getOptions\(\)](#) on page 13-29
- [setOptions\(\)](#) on page 13-32

The following new methods are added to the [Clob Class](#):

- [getOptions\(\)](#) on page 13-40
- [setOptions\(\)](#) on page 13-45

In addition, the behavior of the following methods changed for both [Blob Class](#) and [Clob Class](#): `getChunkSize()` and `copy()`.

### **Runtime Load Balancing of the Stateless Connection Pool**

Information about this feature is in section "[Runtime Load Balancing of the Stateless Connection Pool](#)" on page 12-9.

New APIs for this feature are described in [Chapter 13, "OCI Application Programming Interface"](#):

- A [StatelessConnectionPool Class](#) attribute `PoolType`, defined on page 13-202, has a new option, `NO_RLB`, used to turn off this feature.

### **Fault Diagnosability**

Information about this feature is in section "[Fault Diagnosability](#)" on page 12-9.

---

---

# Introduction to OCCI

This chapter provides an overview of Oracle C++ Call Interface (OCCI) and introduces terminology used in discussing OCCI. You are provided with the background information needed to develop C++ applications that run in an Oracle environment.

This chapter contains these topics:

- [Overview of OCCI](#)
- [Processing of SQL Statements](#)
- [Overview of PL/SQL](#)
- [Special OCCI/SQL Terms](#)
- [Object Support](#)
- [Additional Support](#)

## Overview of OCCI

Oracle C++ Call Interface (OCCI) is an Application Programming Interface (API) that provides C++ applications access to data in an Oracle database. OCCI enables C++ programmers to utilize the full range of Oracle database operations, including SQL statement processing and object manipulation.

OCCI provides for:

- High performance applications through the efficient use of system memory and network connectivity
- Scalable applications that can service an increasing number of users and requests
- Comprehensive support for application development by using Oracle database objects, including client-side access to Oracle database objects
- Simplified user authentication and password management
- n-tiered authentication
- Consistent interfaces for dynamic connection management and transaction management in two-tier client/server environments or multitiered environments
- Encapsulated and opaque interfaces

OCCI provides a library of standard database access and retrieval functions in the form of a dynamic runtime library (OCCI classes) that can be linked in a C++ application at runtime. This eliminates the need to embed SQL or PL/SQL within third-generation language (3GL) programs.

## Benefits of OCI

OCI provides these significant advantages over other methods of accessing an Oracle database:


- Leverages C++ and the Object Oriented Programming paradigm
- Is easy to use
- Is easy to learn for those familiar with JDBC
- Has a navigational interface to manipulate database objects of user-defined types as C++ class instances

Note that OCI does not support non-blocking mode.

## Building an OCI Application

As Figure 1-1 shows, you compile and link an OCI program in the same way that you compile and link an application that does not use the database.

**Figure 1-1 The OCI Development Process**



Oracle supports most popular third-party compilers. The details of linking an OCI program vary from system to system. On some platforms, it may be necessary to include other libraries, in addition to the OCI library, to properly link your OCI programs.



**See Also:** Your operating system-specific Oracle documentation and the *Oracle Database Installation Guide* for more information about compiling and linking an OCCI application for your specific platform

## Functionality of OCCI

OCCI provides the following functionality:

- APIs to design scalable, multithreaded applications that can support large numbers of users securely
- SQL access functions, for managing database access, processing SQL statements, and manipulating objects retrieved from an Oracle database server
- Data type mapping and manipulation functions, for manipulating data attributes of Oracle types
- Advanced Queuing for message management
- XA compliance for distributed transaction support
- Statement caching of SQL and PL/SQL queries
- Connection pooling for managing multiple connections
- Globalization and Unicode support to customize applications for international and regional language requirement
- Object Type Translator Utility
- Transparent Application Failover support

## Procedural and Nonprocedural Elements

Oracle C++ Call Interface (OCCI) enables you to develop scalable, multithreaded applications on multitiered architectures that combine nonprocedural data access power of structured query language (SQL) with procedural capabilities of C++.

In a nonprocedural language program, the set of data to be operated on is specified, but what operations will be performed, or how the operations are to be carried out, is not specified. The nonprocedural nature of SQL makes it an easy language to learn and use to perform database transactions. It is also the standard language used to access and manipulate data in modern relational and object-relational database systems.

In a procedural language program, the execution of most statements depends on previous or subsequent statements and on control structures, such as loops or conditional branches, which are not available in SQL. The procedural nature of these languages makes them more complex than SQL, but it also makes them very flexible and powerful.

The combination of both nonprocedural and procedural language elements in an OCCI program provides easy access to an Oracle database in a structured programming environment.

OCCI supports all SQL data definition, data manipulation, query, and transaction control facilities that are available through an Oracle database server. For example, an OCCI program can run a query against an Oracle database. The queries can require the program to supply data to the database by using input (bind) variables, as follows:

```
SELECT name FROM employees WHERE employee_id = :empnum
```

In this SQL statement, *empnum* is a placeholder for a value that will be supplied by the application.

In an OCCI application, you can also take advantage of PL/SQL, Oracle's procedural extension to SQL. The applications you develop can be more powerful and flexible than applications written in SQL alone. OCCI also provides facilities for accessing and manipulating objects in an Oracle database server.

## Processing of SQL Statements

One of the main tasks of an OCCI application is to process SQL statements. Different types of SQL statements require different processing steps in your program. It is important to take this into account when coding your OCCI application. Oracle recognizes several types of SQL statements:

- Data definition language (DDL) statements
- Control statements
  - Transaction control statements
  - Connection control statements
  - System control statements
- Data manipulation language (DML) statements
- Queries

### DDL Statements

DDL statements manage schema objects in the database. These statements create new tables, drop old tables, and establish other schema objects. They also control access to schema objects. [Example 1-1](#) illustrates how to create a table, and [Example 1-2](#) shows how to grant and revoke privileges on this table.

#### **Example 1-1 Creating a Table**

```
CREATE TABLE employee_information (  
    employee_id NUMBER(6),  
    ssn NUMBER(9),  
    dependents NUMBER(1),  
    mail_address VARCHAR(60))
```

#### **Example 1-2 Specifying Access to a Table**

```
GRANT UPDATE, INSERT, DELETE ON employee_information TO donna  
REVOKE UPDATE ON employee_information FROM jamie
```

DDL statements also allow you to work with objects in the Oracle database, as in [Example 1-3](#), which illustrates how to create an object table.

#### **Example 1-3 Creating an Object Table**

```
CREATE TYPE person_info_type AS OBJECT (  
    employee_id NUMBER(6),  
    ssn NUMBER(9),  
    dependents NUMBER(1),  
    mail_address VARCHAR(60))  
  
CREATE TABLE person_info_table OF person_info_type
```

## Control Statements

OCOCI applications treat transaction control, connection control, and system control statements (for example, DML statements).

**See Also:** *Oracle Database SQL Language Reference* for information about control statements.

## DML SQL Statements

DML statements can change data in database tables. For example, DML statements are used to perform the following actions:

- Insert new rows into a table
- Update column values in existing rows
- Delete rows from a table
- Lock a table in the database
- Explain the execution plan for a SQL statement

DML statements can require an application to supply data to the database by using input bind variables, as in [Example 1–4](#). This statement can be executed several times with different bind values, or several rows can be added through array insert in a single round-trip to the server.

### **Example 1–4 Inserting Data Through Input Bind Variables**

```
INSERT INTO departments VALUES (:1, :2, :3)
```

DML statements also enable you to work with objects in the Oracle Database, as in [Example 1–5](#), which shows the insertion of an instance of a type into an object table.

### **Example 1–5 Inserting Objects into the Oracle Database**

```
INSERT INTO person_info_table
VALUES (person_info_type('450987', '123456789', '3', '146 Winfield Street'))
```

## Queries

Queries are statements that retrieve data from tables in a database. A query can return zero, one, or many rows of data. All queries begin with the SQL keyword `SELECT`, as in [Example 1–6](#):

### **Example 1–6 Using the Simple SELECT Statement**

```
SELECT department_name FROM departments
WHERE department_id = 30
```

Queries can require the program to supply data to the database server by using input bind variables, as in [Example 1–7](#):

### **Example 1–7 Using the SELECT Statement with Input Variables**

```
SELECT first_name, last_name
FROM employees
WHERE employee_id = :emp_id
```

In this SQL statement, `emp_id` is a placeholder for a value that will be supplied by the application.

## Overview of PL/SQL

PL/SQL is Oracle's procedural extension to the SQL language. PL/SQL processes tasks that are more complicated than simple queries and SQL data manipulation language statements. PL/SQL allows a number of constructs to be grouped into a single block and executed as a unit. Among these are the following constructs:

- One or more SQL statements
- Variable declarations
- Assignment statements
- Procedural control statements (IF ... THEN ... ELSE statements and loops)
- Exception handling

In addition to calling PL/SQL stored procedures from an OCCI program, you can use PL/SQL blocks in your OCCI program to perform the following tasks:

- Call other PL/SQL stored procedures and stored functions.
- Combine procedural control statements with several SQL statements, to be executed as a single unit.
- Access special PL/SQL features such as records, tables, cursor FOR loops, and exception handling .
- Use cursor variables
- Access and manipulate objects in an Oracle database

A PL/SQL procedure or function can also return an output variable. This is called an **out bind variable**, as in [Example 1-8](#):

### **Example 1-8 Using PL/SQL to Obtain an Output Variable**

```
GET_EMPLOYEE_NAME (:1, :2);
```

Here, the first parameter is an input variable that provides the ID number of an employee. The second parameter, or the out bind variable, contains the return value of employee name.

PL/SQL can also be used to issue a SQL statement to retrieve values from a table of employees, given a particular employee number. [Example 1-9](#) demonstrates the use of placeholders in PL/SQL statements.

### **Example 1-9 Using PL/SQL to Insert Partial Records into Placeholders**

```
SELECT last_name, first_name, salary, commission_pct  
INTO :emp_last, :emp_first, :sal, :comm  
FROM employees  
WHERE employee_id = :emp_id;
```

Note that the placeholders in this statement are not PL/SQL variables. They represent input and output parameters passed to and from the database server when the statement is processed. These placeholders need to be specified in your program.

## Special OCCI/SQL Terms

This guide uses special terms to refer to the different parts of a SQL statement.

Consider [Example 1-10](#):

**Example 1–10 Using SQL to Extract Partial Records**

```
SELECT first_name, last_name, email
FROM employees
WHERE department_id = 80
AND commission_pct > :base;
```

This example contains these parts:

- A **SQL command**: `SELECT`
- Three **select-list items**: `first_name`, `last_name`, and `email`
- A **table name** in the `FROM` clause: `employees`
- Two **column names** in the `WHERE` clause: `department_id` and `commission_pct`
- A **numeric input value** in the `WHERE` clause: `40`
- A **placeholder** for an input bind variable in the `WHERE` clause: `:base`

When you develop your OCCI application, you call routines that specify to the database server the value of, or reference to, input and output variables in your program. In this guide, specifying the placeholder variable for data is called a **bind operation**. For input variables, this is called an **in bind operation**. For output variables, this is called an **out bind operation**.

## Object Support

OCCI has facilities for working with **object types** and **objects**. An **object type** is a user-defined data structure representing an abstraction of a real-world entity. For example, the database might contain a definition of a `person` object. That object type might have **attributes**, such as `first_name`, `last_name`, and `age`, which represent a person's identifying characteristics.

The object type definition serves as the basis for creating **objects**, which represent instances of the object type. By using the object type as a structural definition, a `person` object could be created with the attributes `John`, `Bonivento`, and `30`. Object types may also contain **methods**, or programmatic functions that represent the behavior of that object type.

OCCI provides a comprehensive API for programmers seeking to use the Oracle database server's object capabilities. These features can be divided into several major categories:

- Client-side object cache
- Runtime environment for objects
- Associative and navigational interfaces to access and manipulate objects
- Metadata class to describe object type metadata
- Object Type Translator (OTT) utility, which maps internal Oracle schema information to client-side language bind variables

**See Also:**

- *Oracle Database Concepts*
- *Oracle Database Object-Relational Developer's Guide* for a more detailed explanation of object types and objects

## Client-Side Object Cache

The object cache is a client-side memory buffer that provides lookup and memory management support for objects. It stores and tracks objects which have been fetched by an OCCI application from the server to the client side. The client-side object cache is created when the OCCI environment is initialized in `object` mode. Multiple applications running against the same server will each have their own object cache. The client-side object cache tracks the objects that are currently in memory, maintains references to objects, manages automatic object swapping and tracks the meta-attributes or type information about objects. The client-side object cache provides the following benefits:

- Improved application performance by reducing the number of client/server round-trips required to fetch and operate on objects
- Enhanced scalability by supporting object swapping from the client-side cache
- Improved concurrency by supporting object-level locking
- Automatic garbage collection when cache thresholds are exceeded

## Runtime Environment for Objects

OCCI provides a runtime environment for objects that offers a set of methods for managing how Oracle objects are used on the client side. These methods provide the necessary functionality for performing these tasks:

- Connecting to an Oracle database server in order to access its object functionality
- Allocating the client-side object cache and tuning its parameters
- Retrieving error and warning messages
- Controlling transactions that access objects in the database
- Associatively accessing objects through SQL
- Describing a PL/SQL procedure or function whose parameters or result are of Oracle object type

## Associative and Navigational Interfaces

Applications that use OCCI can access objects in the database through several types of interfaces:

- SQL `SELECT`, `INSERT`, and `UPDATE` statements
- C++ pointers and references to access objects in the client-side object cache by traversing the corresponding references

OCCI provides a set of methods to support object manipulation by using SQL `SELECT`, `INSERT`, and `UPDATE` statements. To access Oracle objects, these SQL statements use a consistent set of steps as if they were accessing relational tables. OCCI provides methods to access objects by using SQL statements for:

- Binding object type instances and references as input and output variables of SQL statements and PL/SQL stored procedures
- Executing SQL statements that contain object type instances and references
- Fetching object type instances and references
- Retrieving column values from a result set as objects
- Describing a select-list item of an Oracle object type

OCCI provides a seamless interface for navigating objects, enabling you to manipulate database objects in the same way that you would operate on transient C++ objects. You can dereference the overloaded arrow (->) operator on an object reference to transparently materialize the object from the database into the application space.

## Metadata Class

Each Oracle data type is represented in OCCI by a C++ class. The class exposes the behavior and characteristics of the data type by overloaded operators and methods. For example, the Oracle data type NUMBER is represented by the `Number` class.

OCCI provides a metadata class that enables you to retrieve metadata describing database objects, including object types.

## Object Type Translator Utility

The Object Type Translator (OTT) utility translates schema information about Oracle object types into client-side language bindings. That is, OTT translates object type information into declarations of host language variables, such as structures and classes. OTT takes an `intype` file that contains information about Oracle database schema objects as input. OTT generates an `outtype` file and the necessary header and implementation files that must be included in a C++ application that runs against the object schema.

In summary, OCCI supports object handling in an Oracle database by:

- Improving application developer productivity by eliminating the need to write the host language variables that correspond to schema objects
- Maintaining SQL as the data definition language of choice by providing the ability to automatically map Oracle database schema objects created by SQL to host language variables; this allows Oracle to support a consistent, enterprise-wide model of the user's data
- Facilitating schema evolution of object types by regenerating included header files when the schema is changed, allowing Oracle applications to support schema evolution
- Executing SQL statements that manipulate object data and schema information
- Passing object references and instances as input variables in SQL statements
- Declaring object references and instances as variables to receive the output of SQL statements
- Fetching object references and instances from a database
- Describing properties of SQL statements that return object instances and references
- Describing PL/SQL procedures or functions with object parameters or results
- Extending commit and rollback calls to synchronize object and relational functionality
- Advanced queuing of objects

OTT is typically invoked from the command line by specifying the `intype` file, the `outtype` file, and the specific database connection.

## Additional Support

This section discusses how to build the OCCI examples that ship with Oracle Database, and additional resources.

### Building OCCI Demos

You must install the demonstration programs as described in *Oracle Database Examples Installation Guide*. Parts of these demos are used as examples in this book. To build the examples, see the following steps:

1. Navigate to the demo directory.

*On Windows*, this directory is `ORACLE_HOME\rdbms\demo`.

*On Linux and UNIX*, this directory is `ORACLE_HOME/rdbms/demo`.

2. Ensure that this directory contains the file `demo_rdbms.mk`.
3. Create the OCCI demo using the `make` command.

- To make all the demos at the same time, use the following parameters:

```
make -f demo_rdbms.mk occidemos
```

- To make only one demo, use parameters:

```
make -f demo_rdbms.mk demoname
```

- To make a single demo with objects, use parameters:

```
make -f demo_rdbms.mk buildocci EXE=demoname OBJS=demoname.o
```

- To make a single demo with static libraries, use parameters:

```
make -f demo_rdbms.mk buildocci_static EXE=demoname OBJS=demoname.o
```

- For more options, examine the `demo_rdbms.mk` file.

### OCCI on the Oracle Technology Network

You can find additional information on OCCI, including a forum, downloads, and white papers, at:

<http://www.oracle.com/technology/tech/oci/occi/index.html>.



---

---

## Installation and Upgrading

This chapter provides an overview of installation and upgrading for Oracle C++ Call Interface (OCCI).

This chapter contains these topics:

- [Installing Oracle C++ Call Interface](#)
- [Upgrading Considerations](#)
- [Determining the Oracle Database Versions](#)
- [Instant Client](#)
- [Instant Client Light \(English\)](#)
- [Using OCCI with Microsoft Visual C++](#)

### Installing Oracle C++ Call Interface

OCCI is installed as part of the Oracle Database. To determine additional configuration requirements, you should refer to the *Oracle Database Installation Guide* and the *Oracle Database Client Installation Guide* that is specific to your platform.

### Upgrading Considerations

To use the new features available in this release, you must recompile and relink all OCCI applications, including classes generated through the Object Type Translator Utility, when upgrading from an earlier Oracle Client release.

### Determining the Oracle Database Versions

When an application uses several separate code paths that utilize different server versions or client patchsets, you can verify these options both during compilation and at runtime.

### Determining the Oracle Client Version During Compilation

The OCCI header files define `OCCI_MAJOR_VERSION` and `OCCI_MINOR_VERSION` macros. [Example 2-1](#) illustrates one way to use these macros:

**Example 2-1 How to Determine the Major Client Version and Set Performance Features**

```
#if (OCCI_MAJOR_VERSION > 9)
    env->setCacheSortedFlush(true); // benefit of performance, if available
#endif
```

## Determining the Oracle Client and Server Versions at Runtime

During runtime, you can check both the client and server versions of the current `Connection` by using the `getClientVersion()`, `getServerVersion()`, and `getServerVersionUString()` methods.

## Instant Client

The Instant Client feature makes it extremely easy and fast to deploy OCCI based customer application by eliminating the need for `ORACLE_HOME`. The storage space requirements are an additional benefit; Instant Client shared libraries occupy about one-fourth of the disk space required for a full client installation.

### Benefits of Instant Client

- Installation involves copying only four files.
- Storage space requirement for the client is minimal
- No loss of functionality or performance exists for deployed applications
- Simplified packaging with ISV applications

The OCCI Instant Client capability simplifies OCCI installation. Even though OCCI is independent of `ORACLE_HOME` setting in the Instant Client mode, applications that rely on `ORACLE_HOME` settings can continue operation by setting it to the appropriate value. The activation of the Instant Client mode is only dependent on the ability to load the Instant Client data shared library. In particular, this feature allows interoperability with Oracle applications that use `ORACLE_HOME` for their data, but use a newer release of Oracle Client.

### Installing Instant Client

OCCI requires only four shared libraries (or dynamic link libraries, as they are called on some operating systems) to be loaded by the dynamic loader of the operating system. Oracle Database 11g Release 1 (11.1) library names are used; the number part of library names will change to remain consistent with future release numbers.

- **OCI Instant Client Data Shared Library** (`libociei.so` on Linux and UNIX and `oraociei11.dll` on Windows); correct installation of this file determines if you are operating in Instant Client mode
- **Client Code Library** (`libclntsh.so.11.1` on Linux and UNIX and `oci.dll` on Windows)
- **Security Library** (`libnnz11.so` on Linux and UNIX and `orannzsbb11.dll` on Windows)
- **OCCI Library** (`libocci.so.11.1` on Linux and UNIX and `oraocci11.dll` on Windows)

### Oracle Technology Network

The Instant Client libraries are also available on the Oracle Technology Network (OTN) website at:

<http://www.oracle.com/technology/tech/oci/instantclient/>

If these four libraries are accessible through the directory on the OS Library Path variable (`LD_LIBRARY_PATH` on Linux and UNIX and `PATH` on Windows), then OCCI operates in the Instant Client mode. In this mode, there is no dependency on `ORACLE_`

HOME and none of the other code and data files provided in ORACLE\_HOME are needed by OCCI.

If you are installing Instant Client from the Oracle Technology Network,

1. Download and install the Instant Client libraries to an empty directory, such as `instantclient_11_1`.
2. Set the operating system shared library path environment variable (`LD_LIBRARY_PATH` on Linux and UNIX and `PATH` on Windows) to the directory used in step 1, `instantclient_11_1`.

**Instant Client SDK** Instant Client can also be downloaded as an **SDK** package. The SDK contains all necessary header files and a makefile for developing OCCI applications in an Instant Client environment. Once developed, these applications can be deployed in any client environment. The SDK has these additional features:

- It contains C++ demonstration programs.
- It includes libraries required to link applications on Windows, and a `Make.bat` file is provided to build demos.
- The Makefile `demo.mk` is provided to build the demos for Linux and UNIX. The `instantclient_11_1` directory must be on the `LD_LIBRARY_PATH` before linking the application. These programs require symbolic links for the Client Code Library and the OCCI library, `libclntsh.so` and `libocci.so` respectively, in the `instantclient_11_1` directory. The demo Makefile, `demo.mk`, generates these before the link step. These symbolic links can also be created in a shell script:

```
cd instantclient_11_1
ln -s libclntsh.so.11.1 libclntsh.so
ln -s libocci.so.11.1 libocci.so
```

- The SDK also contains the Object Type Translator (OTT) utility and its classes to generate the application header files.

## Complete Client Installation

If you performed a complete client installation by choosing the **Admin** option,

- On Linux or UNIX platforms, the `libociei.so` library can be copied from the `$ORACLE_HOME/instantclient` directory. All the other libraries can be copied from the `$ORACLE_HOME/lib` directory in a full Oracle installation.
- On Windows, the `oraociei11.dll` library can be copied from the `ORACLE_HOME\instantclient` directory. All other Windows libraries can be copied from the `ORACLE_HOME\bin` directory. To use the Microsoft ODBC and OLEDB driver, `ociw32.dll` must also be copied from `ORACLE_HOME\bin`.

## Oracle Universal Installer

If you did not install the database, you can install these libraries by choosing the Instant Client option from the Oracle Universal Installer. After completing these steps, you can begin running OCCI applications.

1. Install the Instant Client shared libraries to a directory such as `instantclient_11_1`.
2. Set the operating system shared library path environment variable to the directory from step 1. For example, on Linux or UNIX, set the `LD_LIBRARY_PATH` to `instantclient_11_1`. On Windows, set `PATH` to locate the `instantclient_11_1` directory.

## Instant Client CD

You can also install Instant Client from the Instant Client CD. You must install Instant Client either in an empty directory or on a different system.

There should be only one set of Oracle libraries on the operating system Library Path variable; if you have several directories or copies of Instant Client libraries, only one directory should be on the operating system Library Path.

Similarly, if you also have an installation on an `ORACLE_HOME` of the same machine, do not place both the `ORACLE_HOME/lib` and Instant Client directory on the operating system Library Path, regardless of the order in which they appear on the Library Path. Only one of `ORACLE_HOME/lib` directory (for non-Instant Client operation) or Instant Client directory (for Instant Client operation) should be on the operating system Library Path variable.

## Using Instant Client

The Instant Client feature is designed for running production applications. For development, use either the Instant Client SDK or a full installation to access OCCI header files, makefiles, demonstration programs, and so on.

## Patching Instant Client Shared Libraries on Unix

This feature is not available on Windows platforms.

Because Instant Client is primarily a deployment feature, one of its design objectives is to reduce the number and size of necessary files. Therefore, Instant Client deployment does not include all files for patching shared libraries. You should use the `OPATCH` utility on an `ORACLE_HOME` based full client to patch the Instant Client shared libraries. The `OPATCH` utility stores the patching information of the `ORACLE_HOME` installation in `libclntsh.so.11.1` for Linux and UNIX. This information can be retrieved using the `genezi` utility:

```
genezi -v
```

If the `genezi` utility is not installed on the machine that deploys Instant Client, you can copy it from the `ORACLE_HOME/bin` directory of the `ORACLE_HOME` machine.

After applying the patch in an `ORACLE_HOME` environment, copy the files listed in "[Installing Instant Client](#)" on page 2-2 to the Instant Client directory.

Instead of copying individual files, you can generate Instant Client `*.zip` files, as described in "[Regenerating the Data Shared Library and Zip Files](#)". Then, instead of copying individual files, you can instead copy the zip files to the target machine and unzip them.

## Regenerating the Data Shared Library and Zip Files

This feature is not available on Windows platforms.

The Instant Client Data Shared Library, `libociei.so`, can be regenerated in a Client Admin Install of `ORACLE_HOME`. Executing the following three lines will create a new `libociei.so` file based on current file in `ORACLE_HOME` and place it in the `ORACLE_HOME/rdbms/install/instantclient` directory; the make target `ilibociei` will generate `libociei.so`:

```
mkdir -p $ORACLE_HOME/rdbms/install/instantclient/light
cd $ORACLE_HOME/rdbms/lib
make -f ins_rdbms.mk ilibociei
```

- 
- 
- Note:** ■ This location of the regenerated data shared library, `libociei.so`, is different from the original location of `ORACLE_HOME/instantclient`
- This script will also create a directory for [Instant Client Light \(English\)](#)
- 
- 

## Database Connection Names for Instant Client

All Oracle net naming methods that do not require use of `ORACLE_HOME` or `TNS_ADMIN` to locate configuration files such as `tnsnames.ora` or `sqlnet.ora` work in the Instant Client mode.

The `connectString` parameter in the [createConnection\(\)](#) call can be specified in the following formats:

- As an **SQL Connect URL string**, of the form:

```
//host:[port][/]service name]
```

such as:

```
//myserver111:5521/bjava21
```

- As an **Oracle Net keyword-value pair**. For example:

```
(DESCRIPTION=(ADDRESS=(PROTOCOL=tcp) (HOST=myserver111) (PORT=5521))
(CONNECT_DATA=(SERVICE_NAME=bjava21)))
```

- As a **connection name** that is resolved through Directory Naming when the site is configured for LDAP server discovery.
- As an **entry** in the `tnsnames.ora` file.

If the `TNS_ADMIN` environment variable is not set, and `TNSNAMES` entries such as `inst1` are used, then the `ORACLE_HOME` variable must be set and the configuration files are expected to be in the `$ORACLE_HOME/network/admin` directory.

Naming methods that require `TNS_ADMIN` to locate configuration files continue to work if the `TNS_ADMIN` environment variable is set.

The `ORACLE_HOME` variable in this case is only used for locating Oracle Net configuration files, and no other component of OCCI Client Code Library uses the value of `ORACLE_HOME`.

The empty `connectString` parameter of [createConnection\(\)](#) is supported by setting the environment variable (`TWO_TASK` on Linux and UNIX, and `LOCAL` on Windows) to one of the four values described earlier.

**See Also:** *Oracle Database Net Services Administrator's Guide* chapter on "Configuring Naming Methods" for more information on connect descriptor

## Environment Variables for OCCI Instant Client

The `ORACLE_HOME` environment variable no longer determines the location of Globalization Support, CORE, and error message files. An OCCI-only application should not require `ORACLE_HOME` to be set. However, if it is set, it does not have an impact on OCCI's operation. OCCI will always obtain its data from the Data Shared Library. If the Data Shared Library is not available, only then is `ORACLE_HOME` used

and a full client installation is assumed. When set, `ORACLE_HOME` should be a valid operating system path name that identifies a directory.

Environment variables `ORA_NLS33`, `ORA_NLS32`, and `ORA_NLS` are ignored in the Instant Client mode.

In the Instant Client mode, if the `ORA_TZFILE` variable is not set, then the smaller, default, `timezone.dat` file from the Data Shared Library is used. If the larger `timezlg.dat` file is to be used from the Data Shared Library, then set the `ORA_TZFILE` environment variable to the name of the file without any absolute or relative path names. That is, on Linux and UNIX:

```
setenv ORA_TZFILE timezlg.dat
```

On Windows:

```
set ORA_TZFILE timezlg.dat
```

If OCCI is not operating in the Instant Client mode because the Data Shared Library is not available, the `ORA_TZFILE` variable, if set, names a complete path name.

If `TNSNAMES` entries are used, then `TNS_ADMIN` directory must contain the `TNSNAMES` configuration files. If `TNS_ADMIN` is not set, the `ORACLE_HOME/network/admin` directory must contain Oracle Net Services configuration files.

## Instant Client Light (English)

Instant Client Light (English) further reduces installation space requirements of the client installation over Instant Client by another 63 MB. Specifically, the installation of the Instant Client Light (English) shared library, `libociicus.so` on Linux and UNIX and `oraociicus11.dll` for Windows, occupies 4 MB on Unix platforms, when the full Instant Client shared library, `libocii.so`, occupies 67 MB of disk space.

Instant Client Light (English), as the name implies, is geared toward applications that require English-only error messages and use either `US7ASCII`, `WE8DEC`, or one of the Unicode character sets. Instant Client Light (English) also has no restrictions on the `TERRITORY` field of the `NLS_LANG` setting. As a result, applications that meet these character set and territory criteria can significantly reduce its footprint if they operate in the Instant Client Light (English) environment.

## Globalization Settings for Instant Client Light (English)

Instant Client Light (English) supports the following character sets:

- Single-byte character sets include `US7ASCII`, `WE8DEC`, `WE8MSWIN1252`, and `WE8ISO8859P1`.
- Unicode character sets include `UTF8`, `AL16UTF16`, and `AL32UTF8`.

Instant Client Light (English) returns an error message if the application attempts to use a character set or a national character set not listed here, either on the client or on the database. The possible error messages, listed here, are only available in English:

- `ORA-12734` Instant Client Light: unsupported client national character set (`NLS_LANG` value set)
- `ORA-12735` Instant Client Light: unsupported client character set (`NLS_LANG` value set)
- `ORA-12736` Instant Client Light: unsupported server national character set (`NLS_LANG` value set)

- ORA-12737 Instant Client Light: unsupported server character set (NLS\_LANG value set)

When setting NLS\_LANG parameters, use the following:

*American\_territory.charset*

where *territory* is any valid Territory that can be specified through NLS\_LANG, and *charset* is one of the character sets already listed in this section.

**See Also:** *Oracle Database Globalization Support Guide* for more information about NLS settings.

## Using Instant Client Light (English)

To determine whether to operate in the Instant Client mode, OCCI applications look for the Data Shared Library on the LD\_LIBRARY\_PATH for Linux and UNIX and PATH on Windows. If this library is not found, OCCI attempts to load the Instant Client Light (English) Data Shared Library, *libociicus.so* for Linux and UNIX and *oraociicus11.dll* on Windows. If neither is found, a full ORACLE\_HOME installation is assumed.

## Installing Instant Client Light (English)

There are three ways to install Instant Client Light (English): from [Oracle Technology Network Download](#), through [Client Admin Install](#), and through [Oracle Universal Installer](#).

---



---

**Note:** All Instant Client and Instant Client Light (English) files should always be copied or installed into an empty directory to ensure that there are no incompatible binaries in the final installation.

---



---

### Oracle Technology Network Download

When installing Instant Client Light (English) from Oracle Technology Network (OTN), download and unzip the *basiclite.zip* package instead of the usual *basic.zip* package. You must ensure that the *instantclient\_11\_1* directory is empty before unzipping the libraries. The downloadable package is at the following URL on OTN:

<http://www.oracle.com/technology/tech/oci/instantclient/>

### Client Admin Install

Instead of copying the Instant Client Data Shared Library from the ORACLE\_HOME/*instantclient* directory, use the Instant Client Light (English) Data Shared Library, *libociicus.so* for Linux and UNIX and *oraociicus11.dll* for Windows, from the ORACLE\_HOME/*instantclient/light* directory. In other words, the Instant Client directory on the LD\_LIBRARY\_PATH for Linux and UNIX and PATH for Windows should contain the smaller Instant Client Light (English) Data Shared Libraries.

### Oracle Universal Installer

If the Instant Client option is selected from the Oracle Universal Installer (OUI), the full Instant Client is installed by default, but the libraries for Instant Client Light (English) are also installed. To operate in Instant Client Light (English) mode, the Instant Client Light (English) Data Shared Library must replace the Instant Client

library. Therefore, you must place `libociicus.so` on the `LD_LIBRARY_PATH` for Linux and UNIX, and `oraociicus11.dll` on the `PATH` for Windows. This design ensures that the Instant Client Light (English) is not enabled by default.

The Instant Client Light (English) Data Shared Library is initially placed in the `ORACLE_HOME/instantclient/light` directory. You must move it to the base directory of the installation, `ORACLE_HOME/instantclient`, and remove the Instant Client Data Shared Library already in that directory.

**Example 2-2 Installing Instant Client Light (English) through Oracle Universal Installer**

If the OUI has installed the Instant Client in `my_oraic_11_1` directory on the `LD_LIBRARY_PATH`, then the following commands would ensure operation in the Instant Client Light (English) mode:

```
cd my_oraic_11_1
rm libociei.so
mv light/libociicus.so .
```

---

---

**Note:** To avoid use of incompatible binary files, all Instant Client files should be copied and installed in an empty directory.

---

---

## Using OCCI with Microsoft Visual C++

The Oracle Database 11gR1 release includes OCCI libraries for developing applications with Microsoft Visual C++ version 8.0 (.NET 2005) Microsoft Visual C++ version 7.1 (.NET 2003). Microsoft Visual C++ version 6.0 is no longer supported.

Microsoft Visual C++ version 7.1 libraries are installed in the following default locations:

```
ORACLE_BASE\ORACLE_HOME\bin\oraocci11.dll
ORACLE_BASE\ORACLE_HOME\oci\lib\msvc\oraocci11.lib
```

Copies of these two files are also installed under the directory:

```
ORACLE_BASE\ORACLE_HOME\oci\lib\msvc\vc71
```

The Microsoft Visual C++ 7.0-specific version of the libraries is installed under:

```
ORACLE_BASE\ORACLE_HOME\oci\lib\msvc\vc7
```

Applications should link with the appropriate OCCI library. You must ensure that the corresponding DLL is located in the Windows system `PATH`.

Applications that link to `MSVCRTD.DLL`, a debug version of Microsoft C-Runtime, `/MDd` compiler flag, should link with these specific OCCI libraries: `oraocci11d.lib` and `oraocci11d.dll`.

All Instant Client packages contain the version of the OCCI DLL that is compatible with Microsoft Visual C++ version 7.1.



---

---

## Relational Programming

This chapter describes the basics of developing C++ applications using Oracle C++ Call Interface (OCI) to work with data stored in relational databases.

This chapter contains these topics:

- [Connecting to a Database](#)
- [Pooling Connections](#)
- [Executing SQL DDL and DML Statements](#)
- [Types of SQL Statements in the OCI Environment](#)
- [Executing SQL Queries](#)
- [Executing Statements Dynamically](#)
- [Committing a Transaction](#)
- [Caching Statements](#)
- [Handling Exceptions](#)

### Connecting to a Database

You have a number of different options with regard to how your application connects to the database.

### Creating and Terminating an Environment

All OCI processing takes place in the context of the `Environment` class. An OCI environment provides application modes and user-specified memory management functions. [Example 3-1](#) illustrates how to create an OCI environment.

**Example 3-1 How to Create an OCI Environment**

```
Environment *env = Environment::createEnvironment();
```

All OCI objects created with the `createxxx()` methods (connections, connection pools, statements) must be explicitly terminated. When appropriate, you must also explicitly terminate the environment. [Example 3-2](#) shows how you terminate an OCI environment.

**Example 3-2 How to Terminate an OCI Environment**

```
Environment::terminateEnvironment(env);
```

In addition, an OCCI environment should have a scope that is larger than the scope of the following object types created in the context of that environment: `Agent`, `Bytes`, `Date`, `Message`, `IntervalDS`, `IntervalYM`, `Subscription`, and `Timestamp`. This rule does not apply to `BFile`, `Blob`, and `Clob` objects, as demonstrated in [Example 3-3](#).

**Example 3-3 How to Use Environment Scope with Blob Objects**

```
const string userName = "HR";
const string password = "password";
const string connectString = "";

Environment *env = Environment::createEnvironment();
{
    Connection *conn = env->createConnection(
        userName, password, connectString);
    Statement *stmt = conn->createStatement(
        "SELECT blobcol FROM mytable");
    ResultSet *rs = stmt->executeQuery();
    rs->next();
    Blob b = rs->getBlob(1);
    cout << "Length of BLOB : " << b.length();
    ...
    stmt->closeResultSet(rs);
    conn->terminateStatement(stmt);
    env->terminateConnection(conn);
}
Environment::terminateEnvironment(env);
```

If the application requires access to objects in the global scope, such as static or global variables, these objects must be set to `NULL` before the environment is terminated. In the preceding example, if `b` was a global variable, a `b.setNull()` call has to be made prior to the `terminateEnvironment()` call.

You can use the `mode` parameter of the `createEnvironment()` method to specify that your application:

- Runs in a threaded environment (`THREADED_MUTEXED` or `THREADED_UNMUTEXED`)
- Uses objects (`OBJECT`)

The mode can be set independently in each environment.

## Opening and Closing a Connection

The `Environment` class is the factory class for creating `Connection` objects. You first create an `Environment` instance, and then use it to enable users to connect to the database by means of the `createConnection()` method.

[Example 3-4](#) creates an environment instance and then uses it to create a database connection for a database user `HR` with the appropriate password.

**Example 3-4 How to Create an Environment and then a Connection to the Database**

```
Environment *env = Environment::createEnvironment();
Connection *conn = env->createConnection("HR", "password");
```

You must use the `terminateConnection()` method shown in the following code example to explicitly close the connection at the end of the working session. In addition, the OCCI environment should be explicitly terminated.

You should remember that all objects (`Refs`, `Bfiles`, `Producers`, `Consumers`, and so on) created or named within a `Connection` instance must be within the inner scope of that instance; the scope of these objects must be explicitly terminated before the `Connection` is terminated. [Example 3-5](#) demonstrates how to terminate the connection and the environment.

**Example 3-5 How to Terminate a Connection to the Database and the Environment**

```
env->terminateConnection(conn);
Environment::terminateEnvironment(env);
```

## Pooling Connections

This section discusses how to use the connection pooling feature of OCCI. The information covered includes the following topics:

- [Using Connection Pools](#)
- [Stateless Connection Pooling](#)

The primary difference between the two is that `StatelessConnectionPools` are used for applications that don't depend on state considerations; these applications can benefit from performance improvements available through use of pre-authenticated connections.

## Using Connection Pools

For many middle-tier applications, connections to the database should be enabled for a large number of threads. Because each thread exists for a relatively short time, opening a connection to the database for every thread would be inefficient use of connections, and would result in poor performance.

By employing the **connection pooling** feature, your application can create a small set of connections available to a large number of threads, enabling you to use database resources very efficiently.

### Creating a Connection Pool

To create a connection pool, you use the `createConnectionPool()` method on page 13-87, as demonstrated in [Example 3-6](#).

**Example 3-6 The `createConnectionPool()` Method**

```
virtual ConnectionPool* createConnectionPool(
    const string &poolUserName,
    const string &poolPassword,
    const string &connectString = "",
    unsigned int minConn = 0,
    unsigned int maxConn = 1,
    unsigned int incrConn = 1) = 0;
```

The following parameters are used in [Example 3-6](#):

- `poolUserName`: The owner of the connection pool
- `poolPassword`: The password to gain access to the connection pool
- `connectString`: The database name that specifies the database server to which the connection pool is related

- `minConn`: The minimum number of connections to be opened when the connection pool is created
- `maxConn`: The maximum number of connections that can be maintained by the connection pool. When the maximum number of connections are open in the connection pool, and all the connections are busy, an OCCI method call that needs a connection waits until it gets one, unless `setErrorOnBusy()` was called on the connection pool
- `incrConn`: The additional number of connections to be opened when all the connections are busy and a call needs a connection. This increment is implemented only when the total number of open connections is less than the maximum number of connections that can be opened in that connection pool.

[Example 3-7](#) demonstrates how you can create a connection pool.

#### **Example 3-7 How to Create a Connection Pool**

```
const string connectString = "";
unsigned int maxConn = 5;
unsigned int minConn = 3;
unsigned int incrConn = 2;

ConnectionPool *connPool = env->createConnectionPool(
    poolUserName,
    poolPassword,
    connectString,
    minConn,
    maxConn,
    incrConn);
```

You can also configure all these attributes dynamically. This lets you design an application that has the flexibility of reading the current load (number of open connections and number of busy connections) and tune these attributes appropriately. In addition, you can use the `setTimeout()` method to time out the connections that are idle for more than the specified time. The OCCI terminates idle connections periodically so as to maintain an optimum number of open connections.

There is no restriction that one environment must have only one connection pool. There can be multiple connection pools in a single OCCI environment, and these can connect to the same or different databases. This is useful for applications requiring load balancing.

### **Proxy Connections**

If you authorize the connection pool user to act as a proxy for other connections, then no password is required to log in database users who use one of the connections in the connection pool.

A proxy connection can be created by using either of the following two versions of the [createProxyConnection\(\)](#) method on page 13-63, demonstrated in [Example 3-8](#).

#### **Example 3-8 The createProxyConnection() Method**

```
ConnectionPool->createProxyConnection(
    const string &username,
    Connection::ProxyType proxyType = Connection::PROXY_DEFAULT);
```

or

```
ConnectionPool->createProxyConnection(
```

```

const string &username,
string roles[],
int numRoles,
Connection::ProxyType proxyType = Connection::PROXY_DEFAULT);

```

The following parameters are used in the previous method example:

- `roles[]`: The roles array specifies a list of roles to be activated after the proxy connection is activated for the client
- `Connection::ProxyType proxyType = Connection::PROXY_DEFAULT`: The enumeration `Connection::ProxyType` lists constants representing the various ways of achieving proxy authentication. `PROXY_DEFAULT` is used to indicate that name represents a database username and is the only proxy authentication mode currently supported.

## Stateless Connection Pooling

Stateless Connection Pooling is specifically designed for use in applications that require short connection times and don't need to deal with state considerations. The primary benefit of Stateless Connection Pooling is increased performance, since the time consuming connection and authentication protocols are eliminated.

Stateless Connection Pools create and maintain a group of stateless, authenticated connection to the database that can be used by multiple threads. Once a thread finishes using its connection, it should release the connection back to the pool. If no connections are available, new ones are generated. Thus, the number of connections in the pool can increase dynamically.

Some of the connections in the pool may be tagged with specific properties. The user may request a default connection, set certain attributes, such as Globalization Support settings, then tag it and return it to the pool. When a connection with same attributes is needed, a request for a connection with the same tag can be made, and one of several connections in the pool with the same tag can be reused. The tag on a connection can be changed or reset.

Proxy connections may also be created and maintained through the Stateless Connection Pooling interface.

Stateless connection pooling improves the scalability of the mid-tier applications by multiplexing the connections. However, connections from a `StatelessConnectionPool` should not be used for long transactions, as holding connections for long periods leads to reduced concurrency.

---



---

### Caution:

- OCCI will not check for the correctness of the connection-tag pair. You are responsible for ensuring that connections with different client-side properties do not have the same tag.
  - Your application should commit or rollback any open transactions before releasing the connection back to the pool. If this is not done, Oracle automatically *commits* any open transactions when the connection is released.
- 
- 

There are two types of stateless connection pools:

- A **homogeneous pool** is one in which all the connections will be authenticated with the username and password provided at the time of creation of the pool.

Therefore, all connections will have the same authentication context. Proxy connections are not allowed in such pools.

- Different connections can be authenticated by different usernames in **heterogeneous pools**. Proxy connections can also exist in heterogeneous pools, provided the necessary privileges for creating them are granted on the server.

[Example 3–9](#) illustrates a basic usage scenario for connection pools. [Example 3–10](#) presents the usage scenario for creating and using a homogeneous stateless connection pool, while [Example 3–11](#) covers the use of heterogeneous pools.

#### **Example 3–9 How to Use a StatelessConnectionPool**

Because the pool size is dynamic, in response to changing user requirements, up to the specified maximum number of connections. Assume that a stateless connection pool is created with the following parameters:

- `minConn = 5`
- `incrConn = 2`
- `maxConn = 10`

Five connections are opened when the pool is created:

- `openConn = 5`

Using `get [AnyTagged] [Proxy]Connection()` methods, the user consumes all 5 open connections:

- `openConn = 5`
- `busyConn = 5`

When the user wants another connection, the pool will open 2 new connections and return one of them to the user

- `openConn = 7`
- `busyConn = 6`

The upper limit for the number of connections that can be pooled is `maxConn` specified at the time of creation of the pool.

The user can also modify the pool parameters after the pool is created using the call to `setPoolSize()` method.

If a heterogeneous pool is created, the `incrConn` and `minConn` arguments are ignored.

#### **Example 3–10 How to Create and Use a Homogeneous Stateless Connection Pool**

To create a homogeneous stateless connection pool, follow these basic steps and pseudocode commands:

1. Create a stateless connection pool in the `HOMOGENEOUS` mode of the `Environment` with a `createStatelessConnectionPool()` call.

```
StatelessConnectionPool *scp =
    env->createStatelessConnectionPool(
        username, passwd, connectString, maxCon, minCon, incrCon,
        StatelessConnectionPool::HOMOGENEOUS );
```

2. Get a new or existing connection from the pool by calling the `getConnection()` method.

```
Connection *conn=scp->getConnection(tag);
```

During the execution of this call, the pool is searched for a connection with a matching tag. If such a connection exists, it is returned to the user. Otherwise, an untagged connection authenticated by the pool username and password is returned.

Alternatively, you can obtain a connection with `getAnyTaggedConnection()` call. It will return a connection with a non-matching tag if neither a matching tag or `NULL` tag connections are available. You should verify the tag returned by a `getTag()` call on `Connection`.

```
Connection *conn=scp->getAnyTaggedConnection(tag);
string tag=conn->getTag();
```

3. Use the connection.
4. Release the connection to the `StatelessConnectionPool` through the `releaseConnection()` call.

```
scp->releaseConnection(conn, tag);
```

An empty tag, "", untags the `Connection`.

You have an option of retrieving the connection from the `StatelessConnectionPool` using the same tag parameter value in a `getConnection()` call.

```
Connection *conn=scp->getConnection(tag);
```

Instead of returning the `Connection` to the `StatelessConnectionPool`, you may wish to destroy it using the `terminateConnection()` call.

```
scp->terminateConnection(conn);
```

5. Destroy the pool through `terminateStatelessConnectionPool()` call on the `Environment` object.

```
env->terminateStatelessConnectionPool(scp);
```

### **Example 3–11 How to Create and Use a Heterogeneous Stateless Connection Pool**

To create a heterogeneous stateless connection pool, follow these basic steps and pseudocode commands:

1. Create a stateless connection pool in the `HETEROGENEOUS` mode of the `Environment` with a `createStatelessConnectionPool()` call.

```
StatelessConnectionPool *scp =
    env->createStatelessConnectionPool(
        username, passwd, connectString, maxCon, minCon, incrCon,
        StatelessConnectionPool::HETEROGENEOUS);
```

2. Get a new or existing connection from the pool by calling the `getConnection()` method of the `StatelessConnectionPool` that is overloaded for the heterogeneous pool option.

```
Connection *conn=scp->getConnection(username, passwd, tag);
```

During the execution of this call, the heterogeneous pool is searched for a connection with a matching tag. If such a connection exists, it is returned to the user. Otherwise, an appropriately authenticated untagged connection with a `NULL` tag is returned.

Alternatively, you can obtain a connection with `getAnyTaggedConnection()` call that has been overloaded for heterogeneous pools. It will return a connection with a non-matching tag if neither a matching tag or `NULL` tag connections are available. You should verify the tag returned by a `getTag()` call on `Connection`.

```
Connection *conn=scp->getAnyTaggedConnection(username, passwd, tag);
string tag=conn->getTag();
```

You may also wish to use proxy connections by `getProxyConnection()` or `getAnyTaggedProxyConnection()` calls on the `StatelessConnectionPool`.

```
Connection *pconn = scp->getProxyConnection(proxyName, roles{,
                                           nuRoles, tag, proxyType);
Connection *pconn = scp->getAnyTaggedProxyConnection( proxyName, tag,
                                                    proxyType);
```

3. Use the connection.
4. Release the connection to the `StatelessConnectionPool` through the `releaseConnection()` call.

```
scp->releaseConnection(conn, tag);
```

An empty tag, "", untags the `Connection`.

You have an option of retrieving the connection from the `StatelessConnectionPool` using the same tag parameter value in a `getConnection()` call.

```
Connection *conn=scp->getConnection(tag);
```

Instead of returning the `Connection` to the `StatelessConnectionPool`, you may wish to destroy it using the `terminateConnection()terminateStatelessConnectionPool()` call.

```
scp->terminateConnection(conn);
```

5. Destroy the pool through a `terminateStatelessConnectionPool()` call on the `Environment` object.

```
env->terminateStatelessConnectionPool(scp);
```

## Database Resident Connection Pooling

Enterprise-level applications must typically handle a high volume of simultaneous user sessions that are implemented as persistent connections to the database. The memory overhead of creating and managing these connections has significant implications for the performance of the database.

Database Resident Connection Pooling solves the problem of too many persistent connections by providing a pool of dedicated servers for handling a large set of application connections, thus enabling the database to scale to tens of thousands of simultaneous connections. It significantly reduces the memory footprint on the database tier and increases the scalability of both the database and middle tiers. Database Resident Connection Pooling is designed for architectures with multi-process application servers and multiple middle tiers that cannot accommodate connection pooling in the middle tier.

Database Resident Connection Pooling architecture closely follows the default dedicated model for connecting to an Oracle Database instance; however, it removes the overhead of assigning a specific server to each connection. On the server tier, a



majority of connections are inactive at any given time, and each of these connections consumes memory. Because of this, database systems that support high connection volumes face the risk of quickly exhausting all available memory. Database Resident Connection Pooling allows a connection to use a dedicated server, which combines an Oracle server process and a user session. Once the connection becomes inactive, it returns its resources to the pool, for use by similar connections.

In multithreaded middle tiers that are capable of comprehensive connection pooling, the issue of unused connections is somewhat different. As the number of middle tiers increases, each middle tier privately holds a number of connections to the database; these connections cannot be shared with other middle tiers. Locating the connection pool on the database instead enables the sharing of connections across similar clients.

Database Resident Connection Pooling supports password-based authentication, statement caching, tagging, and Fast Application Notification. You can also use client-side stateless connection pooling in conjunction with the database resident connection pooling.

Note that clients that hold connections from the database resident connection pool are persistently connected to a background Connection Broker process. The Connection Broker implements the pool functionality and multiplexes inbound client connections to a pool of dedicated server processes. Clients that do not use the connection pool use dedicated server processes instead.

**See Also:**

- *Oracle Database Concepts* for details about the architecture of Database Resident Connection Pooling
- *Oracle Database Administrator's Guide* for details on configuring Database Resident Connection Pooling
- *Oracle Database PL/SQL Packages and Types Reference*, for the `DBMS_CONNECTION_POOL` package

## Administering Database Resident Connection Pools

To implement database resident connection pooling, it must first be enabled on the system by a user with `SYSDBA` privileges. See [Example 3–12](#) for steps necessary to initiate and maintain a database resident connection pool.

### **Example 3–12 How to Administer the Database Resident Connection Pools**

A user with `SYSDBA` privileges must perform the next steps.

1. Connect to the database.

```
SQLPLUS / AS SYSDBA
```

2. [Optional] Configure the parameters of the database resident connection pool. The default values of a pool are set in the following way:

```
DBMS_CONNECTION_POOL.CONFIGURE_POOL( 'SYS_DEFAULT_CONNECTION_POOL',
                                       MIN=>10,
                                       MAX=>200);
```

3. [Optional] Alter specific parameters of the database resident connection pool without affecting other parameters.

```
DBMS_CONNECTION_POOL.ALTER_PARAM( 'SYS_DEFAULT_CONNECTION_POOL',
                                   'INACTIVITY_TIMEOUT',
                                   10);
```

4. Start the connection pool. After this step, the connection pool is available to all qualified clients.

```
DBMS_CONNECTION_POOL.START_POOL( 'SYS_DEFAULT_CONNECTION_POOL');
```

5. [Optional] Change the parameters of the database resident connection pool.

```
DBMS_CONNECTION_POOL.ALTER_PARAM( 'SYS_DEFAULT_CONNECTION_POOL',
                                   'MAXSIZE',
                                   20);
```

6. [Optional] The configuration of the connection pool can be reset to default values.

```
DBMS_CONNECTION_POOL.RESTORE_DEFAULTS ( 'SYS_DEFAULT_CONNECTION_POOL');
```

7. Stop the pool. Note that pool information is persistent: stopping the pool does not destroy the pool name and configuration parameters.

```
DBMS_CONNECTION_POOL.STOP_POOL();
```

Note that in Oracle RAC configurations, the database resident connection pool starts on all configured nodes. If the pool is not stopped, the starting configuration is persistent across instance restarts: the pool is started automatically when the instance comes up.

## Using Database Resident Connection Pools

To use database resident connection pooling, you must specify the connection class and connection purity. If the application requests a connection that cannot be potentially tainted with prior connection state, it must specify purity as `NEW`; Oracle recommends this approach if clients from different geographic locale settings share the same database instance. When the application can use a previously used connection, the purity should be set to `SELF`. In conjunction with connection class and purity specifications, you can also use an application-specific tags to choose a previously used connection that has the desired state. The default connection pool name, as demonstrated in [Example 3-12](#), is `SYS_DEFAULT_CONNECTION_POOL`.

This feature overloads [StatelessConnectionPool Class](#) and [Environment Class](#) interfaces for retrieving a connection (`getConnection()` and `getProxyConnection()`) by adding the parameters that specify connection class and purity. Every connection request outside of a client-side connection pool has a default purity of `NEW`. Connection requests in the context of a client-side connection pool have a default purity of `SELF`.

### **Example 3-13 How to Get a Connection from a Database Resident Connection Pool**

```
conn1 = env->createConnection (/*username */"hr",
                              /*password*/ "password", /* database*/ "inst1_cmon",
                              /* connection class */"TESTCC", /* purity */"Connection::SELF");
stmt1 = conn1->createStatement("select count(*) from emp");
rs=stmt1->executeQuery();
while (rs->next())
{
    int num = rs->getInt(1);
    sprintf((char *)tmp, "%d", num);
    cout << tmp << endl;
}
stmt1->closeResultSet(rs);
conn1->terminateStatement(stmt1);
env->terminateConnection(conn1);
```

**Example 3–14 Using Client-Side Pool and Server-Side Pool**

```

StatelessConnectionPool *scPool;
OCIConnection *conn1, *conn2;
scPool = env->createStatelessConnectionPool
    (poolUserName, poolPassword, connectString, maxConn,
     minConn, incrConn, StatelessConnectionPool::HOMOGENEOUS);

conn1= scPool->getConnection( /* Connection class name */"TESTCC",
                             /* Purity */ Connection::SELF);
/* or, for proxy connections */
conn2= scPool->getProxyConnection(/* username*/ "HR_PROXY",
                                 /*Connection class */"TESTCC", /* Purity */Connection::SELF);
/* or, for getting a tagged connection */
conn3 = scPool->getConnection(/*connection class */"TESTCC",
                              /*purity*/ Connection::SELF,
                              /*tag*/ "TESTTAG");
/* Releasing a tagged connection is the same as is done presently */
scPool->releaseConnection(conn3, "TESTTAG");

/* In order to specify purity as new */
conn4 = scPool->getConnection(/* connection class */"TESTCC",/* purity of new */
                              Connection::NEW);

/* Get a connection using username and password */
conn5 = scPool->getConnection (username, password,"TESTCC", Connection::SELF);

/* Using roles when asking for a connection */
conn6 = scPool->getProxyConnection (username, roles, nRoles,"TESTCC",
                                    Connection::SELF);

...

/* The other code continues as is...writing for the sake of clarity */
...
stmt1=conn1->createStatement ("INSERT INTO emp values (:c1, :c2)");
stmt1->setInt(1, thrid);
stmt1->setString(2, "Test");
int count = stmt1->executeUpdate ();
conn1->commit();
conn1->terminateStatement(stmt1);
/* Release the connection */
scPool->releaseConnection (conn1);
...
env->terminateStatelessConnectionPool (scPool);

```

## Executing SQL DDL and DML Statements

SQL is the industry-wide language for working with relational databases. In OCI you execute SQL commands through the `Statement` class.

### Creating a Statement Object

To create a `Statement` object, call the `createStatement()` method of the `Connection` object, as demonstrated in [Example 3–15](#),

**Example 3–15 How to Create a Statement**

```
Statement *stmt = conn->createStatement();
```

## Creating a Statement Object that Executes SQL Commands

Once you have created a `Statement` object, execute SQL commands by calling the `execute()`, `executeUpdate()`, `executeArrayUpdate()`, or `executeQuery()` methods on the `Statement` object. These methods are used for the following purposes:

- `execute()` executes all nonspecific statement types
- `executeUpdate()` executes DML and DDL statements
- `executeArrayUpdate()` executes multiple DML statements
- `executeQuery()` executes a query

### Creating a Database Table

[Example 3-16](#) demonstrates how you can create a database table using the `executeUpdate()` method.

#### **Example 3-16 How to Create a Database Table Using the `executeUpdate()` Method**

```
stmt->executeUpdate("CREATE TABLE shopping_basket
    (item_number VARCHAR2(30), quantity NUMBER(3))");
```

### Inserting Values into a Database Table

Similarly, you can execute a SQL `INSERT` statement by invoking the `executeUpdate()` method, as demonstrated in [Example 3-17](#).

#### **Example 3-17 How to Add Records Using the `executeUpdate()` Method**

```
stmt->executeUpdate("INSERT INTO shopping_basket
    VALUES ('MANGO', 3)");
```

The `executeUpdate()` method returns the number of rows affected by the SQL statement.

**See Also:** `$ORACLE_HOME/rdbms/demo` for a code example that demonstrates how to perform insert, select, update, and delete operations on the table row.

## Reusing the Statement Object

You can reuse a `Statement` object to execute SQL statements multiple times. To repeatedly execute the same statement with different parameters, you should specify the statement by the `setSQL()` method of the `Statement` object on page 13-244, as demonstrated in [Example 3-18](#).

#### **Example 3-18 How to Specify a SQL Statement Using the `setSQL()` Method**

```
stmt->setSQL("INSERT INTO shopping_basket VALUES (:1, :2)");
```

You may now execute this `INSERT` statement as many times as required. If at a later time you wish to execute a different SQL statement, you simply reset the statement object, as demonstrated in [Example 3-19](#).

#### **Example 3-19 How to Reset a SQL Statement Using the `setSQL()` Method**

```
stmt->setSQL("SELECT * FROM shopping_basket WHERE quantity >= :1");
```

By using the `setSQL()` method on page 13-244, OCCI statement objects and their associated resources are not allocated or freed unnecessarily. To retrieve the contents of the current statement object at any time, use the `getSQL()` method on page 13-225.

## Terminating a Statement Object

You should explicitly terminate and deallocate a Statement object using the `terminateStatement()` method on page 13-59, as demonstrated in [Example 3-20](#).

### *Example 3-20 How to Terminate a Statement Using the terminateStatement() Method*

```
Connection::conn->terminateStatement(Statement *stmt);
```

## Types of SQL Statements in the OCCI Environment

There are three types of SQL statements in the OCCI environment:

- **Standard Statements** use SQL commands with specified values
- **Parameterized Statements** have parameters, or bind variables
- **Callable Statements** call stored PL/SQL procedures and functions

The methods of the [Statement Class](#) are subdivided into those applicable to all statements, to parameterized statements, and to callable statements. Standard statements are a superset of parameterized statements, and parameterized statements are a superset of callable statements.

### Standard Statements

Both [Example 3-16](#) and [Example 3-17](#) demonstrate **standard statements** in which you must explicitly define the values of the statement. In [Example 3-16](#), the CREATE TABLE statement specifies the name of the table `shopping_basket`. In [Example 3-17](#), the INSERT statement stipulates the values that will be inserted into the table, (`'MANGO', 3`).

### Parameterized Statements

You can execute the same statement with different parameters by setting placeholders for the input variables of the statement. These statements are referred to as **parameterized statements** because they can accept parameter input from a user or a program.

If you want to execute an INSERT statement with different parameters, you must first specify the statement by the `setSQL()` method of the Statement object on page 13-244, as demonstrated in [Example 3-18](#).

You then call the `setxxx()` methods to specify the parameters, where `xxx` stands for the type of the parameter. Provided that the value of the statement object is `"INSERT INTO shopping_basket VALUES (:1, :2)"`, as specified in [Example 3-18](#), you can use the code in [Example 3-21](#) to invoke the `setString()` method on page 13-244 and `setInt()` method on page 13-239 to input the values of these types into the first and second parameters, and the `executeUpdate()` method on page 13-218 to insert the new row into the table. You can re-use the statement object by re-setting the parameters and once again calling the `executeUpdate()` method on page 13-218. If your application is executing the same statement repeatedly, you should avoid changing the input parameter types because this initiates a rebind operation, and affects application performance.

**Example 3–21 How to Use setxxx() Methods to Set Individual Column Values**

```

stmt->setString(1, "Banana");    // value for first parameter
stmt->setInt(2, 5);             // value for second parameter
stmt->executeUpdate();         // execute statement
...
stmt->setString(1, "Apple");    // value for first parameter
stmt->setInt(2, 9);            // value for second parameter
stmt->executeUpdate();         // execute statement

```

**Callable Statements**

PL/SQL stored procedures, as their name suggests, are procedures that are stored on the database server for reuse by an application. In OCCI, a **callable statement** is a call to a procedure which contains other SQL statements.

If you wish to call a procedure `countGroceries()`, that returns the quantity of a specified kind of fruit, you must first specify the input parameters of a PL/SQL stored procedure through the `setXXX()` methods of the `Statement` class, as demonstrated in [Example 3–22](#).

**Example 3–22 How to Specify the IN Parameters of a PL/SQL Stored Procedure**

```

stmt->setSQL("BEGIN countGroceries(:1, :2); END:");
int quantity;
stmt->setString(1, "Apple");    // specify the first (IN) parameter of procedure

```

However, before calling a stored procedure, you need to specify the type and size of any OUT parameters by calling the `registerOutParam()` method on page 13-231, as demonstrated in [Example 3–23](#). For IN/OUT parameters, use the `setXXX()` methods to pass in the parameter, and `getXXX()` methods to retrieve the results.

**Example 3–23 How to Specify OUT Parameters of a PL/SQL Stored Procedure**

```

stmt->registerOutParam(2, Type::OCCIINT, sizeof(quantity));
    // specify type and size of the second (OUT) parameter

```

You now execute the statement by calling the procedure:

```

stmt->executeUpdate();         // call the procedure

```

Finally, you obtain the output parameters by calling the relevant `getxxx()` method:

```

quantity = stmt->getInt(2);    // get value of the second (OUT) parameter

```

**Callable Statements that Use Array Parameters**

A PL/SQL stored procedure executed through a callable statement can have array of values as parameters. The number of elements in the array and the dimension of elements in the array are specified through the `setDataBufferArray()` method.

The following example shows the `setDataBufferArray()` method:

```

void setDataBufferArray(
    unsigned int paramIndex,
    void *buffer,
    Type type,
    ub4 arraySize,
    ub4 *arrayLength,
    sb4 elementSize,
    ub2 *elementLength,
    sb2 *ind = NULL,

```

```
ub2 *rc = NULL);
```

The following parameters are used in the previous method example:

- `paramIndex`: Parameter number
- `buffer`: Data buffer containing an array of values
- `Type`: Type of data in the data buffer
- `arraySize`: Maximum number of elements in the array
- `arrayLength`: Number of elements in the array
- `elementSize`: Size of the current element in the array
- `elementLength`: Pointer to an array of lengths. `elementLength[i]` has the current length of the *i*th element of the array
- `ind`: Indicator information
- `rc`: Returns code

## Streamed Reads and Writes

OCCI supports a streaming interface for insertion and retrieval of very large columns by breaking the data into a series of small chunks. This approach minimizes client-side memory requirements. This streaming interface can be used with parameterized statements such as `SELECT` and various DML commands, and with callable statements in PL/SQL blocks. The data types supported by streams are `BLOB`, `CLOB`, `LONG`, `LONG RAW`, `RAW`, and `VARCHAR2`.

Streamed data is of three kinds:

- A **writable** stream corresponds to a bind variable in a `SELECT`/`DML` statement or an `IN` argument in a callable statement.
- A **readable** stream corresponds to a fetched column value in a `SELECT` statement or an `OUT` argument in a callable statement.
- A **bidirectional** stream corresponds to an `IN`/`OUT` bind variable.

Methods of the [Stream Class](#) support the stream interface.

The `getStream()` method of the [Statement Class](#) returns a stream object that supports reading and writing for DML and callable statements:

- For writing, it passes data to a bind variable or to an `IN` or `IN`/`OUT` argument
- For reading, it fetches data from an `OUT` or `IN`/`OUT` argument

The `getStream()` method of the [ResultSet Class](#) returns a stream object that can be used for reading data.

The `status()` method of these classes determines the status of the streaming operation.

### Binding Data in Streaming Mode; `SELECT`/`DML` and `PL/SQL`

To bind data in a streaming mode, follow these steps and review [Example 3-24](#):

1. Create a `SELECT`/`DML` or `PL/SQL` statement with appropriate bind placeholders.
2. Call the `setBinaryStreamMode()` or `setCharacterStreamMode()` method of the [Statement Class](#) for each bind position that will be used in the streaming mode. If the bind position is a `PL/SQL` `IN` or `IN`/`OUT` argument type, indicate this by

calling the three-argument versions of these methods and setting the `inArg` parameter to `TRUE`.

3. Execute the statement; the `status()` method of the [Statement Class](#) will return `NEEDS_STREAM_DATA`.
4. Obtain the stream object through a `getStream()` method of the [Statement Class](#).
5. Use `writeBuffer()` and `writeLastBuffer()` methods of the [Stream Class](#) to write data.
6. Close the stream with `closeStream()` method of the [Statement Class](#).
7. After all streams are closed, the `status()` method of the [Statement Class](#) will change to an appropriate value, such as `UPDATE_COUNT_AVAILABLE`.

### **Example 3–24 How to Bind Data in a Streaming Mode**

```
Statement *stmt = conn->createStatement(
    "Insert Into testtab(longcol) values (:1)"; //longcol is LONG type column
stmt->setCharacterStreamMode(1, 100000);
stmt->executeUpdate();

Stream *instream = stmt->getStream(1);
char buffer[1000];
instream->writeBuffer(buffer, len);           //write data
instream->writeLastBuffer(buffer, len);      //repeat
stmt->closeStream(instream);                 //stmt->status() is
                                             //UPDATE_COUNT_AVAILABLE

Statement *stmt = conn->createStatement("BEGIN testproc(:1); END;");

//if the argument type to testproc is IN or IN/OUT then pass TRUE to
//setCharacterStreamMode or setBinaryStreamMode
stmt->setBinaryStreamMode(1, 100000, TRUE);
```

### **Fetching Data in Streaming Mode: PL/SQL**

To fetch data from a streaming mode, follow these steps and review [Example 3–25](#):

1. Create a `SELECT/DML` statement with appropriate bind placeholders.
2. Call the `setBinaryStreamMode()` or `setCharacterStreamMode()` method of the [Statement Class](#) for each bind position into which data will be retrieved from the streaming mode.
3. Execute the statement; the `status()` method of the [Statement Class](#) will return `STREAM_DATA_AVAILABLE`.
4. Obtain the stream object through a `getStream()` method of the [Statement Class](#).
5. Use `readBuffer()` and `readLastBuffer()` methods of the [Stream Class](#) to read data.
6. Close the stream with `closeStream()` method of the [Statement Class](#).

### **Example 3–25 How to Fetch Data in a Streaming Mode Using PL/SQL**

```
Statement *stmt = conn->createStatement("BEGIN testproc(:1); END;");
    //argument 1 is OUT type
stmt->setCharacterStreamMode(1, 100000);
stmt->execute();

Stream *outarg = stmt->getStream(1);
    //use Stream::readBuffer/readLastBuffer to read data
```



## Fetching Data in Streaming Mode: ResultSet

[Executing SQL Queries](#) and [Example 3-27](#) on page 3-20 provide an explanation of how to use the streaming interface with result sets.

### Working with Multiple Streams

If you have to work with multiple read and write streams, you have to ensure that the read or write of one stream is completed prior to reading or writing on another stream. To determine stream position, use the `getCurrentStreamParam()` method of the [Statement Class](#) or the `getCurrentStreamColumn()` method of the [ResultSet Class](#). The `status()` method of the [Stream Class](#) will return `READY_FOR_READ` if there is data in the stream available for reading, or it will return `INACTIVE` if all the data has been read, as described in [Table 13-44](#). The application can then read the next streaming column. [Example 3-26](#) demonstrates how to read and write with two concurrent streams.

#### **Example 3-26 How to Read and Write with Multiple Streams**

```
Statement *stmt = conn->createStatement(
    "Insert into testtab(longcol1, longcol2) values (:1,:2)");
    //longcol1 AND longcol2 are 2 columns inserted in streaming mode

stmt->setBinaryStreamMode(1, 100000);
stmt->setBinaryStreamMode(2, 100000);
stmt->executeUpdate();

Stream *col1 = stmt->getStream(1);
Stream *col2 = stmt->getStream(2);

col1->writeBuffer(buffer, len);           //first stream
...                                     //complete writing col1 stream

col1->writeLastBuffer(buffer, len);      //finish first stream and move to col2

col2->writeBuffer(buffer, len);          //second stream

//reading multiple streams
stmt = conn->createStatement("select longcol1, longcol2 from testtab");
ResultSet *rs = stmt->executeQuery();
rs->setBinaryStreamMode(1, 100000);
rs->setBinaryStreamMode(2, 100000);

while (rs->next())
{
    Stream *s1 = rs->getStream(1)
    while (s1->status() == Stream::READY_FOR_READ)
    {
        s1->readBuffer(buffer,size);    //process
    }
    //first streaming column done
    rs->closeStream(s1);

    //move onto next column. rs->getCurrentStreamColumn() will return 2

    Stream *s2 = rs->getStream(2)
    while (s2->status() == Stream::READY_FOR_READ)
    {
        s2->readBuffer(buffer,size);    //process
    }
    //close the stream
    rs->closeStream(s2);
}
```

}

---

---

**Note:** It is not possible to use these streaming interfaces together with the `setDataBuffer()` method in the same `Statement` and `ResultSet` objects.

---

---

**See Also:** ["Application Managed Data Buffering"](#) on page 12-5 in [Chapter 12, "Optimizing Performance of OCCI Applications"](#)

## Modifying Rows Iteratively

While you can issue the `executeUpdate` method repeatedly for each row, OCCI provides an efficient mechanism for sending data for multiple rows in a single network round-trip. To do this, use the `addIteration()` method of the `Statement` class to perform batch operations that modify a different row with each iteration.

To execute `INSERT`, `UPDATE`, and `DELETE` operations iteratively, you must:

- Set the maximum number of iterations
- Set the maximum parameter size for variable length parameters

### Setting the Maximum Number of Iterations

For iterative execution, first specify the maximum number of iterations that would be done for the statement by calling the `setMaxIterations()` method:

```
Statement->setMaxIterations(int maxIterations);
```

You can retrieve the current maximum iterations setting by calling the `getMaxIterations()` method.

### Setting the Maximum Parameter Size

If the iterative execution involves variable length data types, such as `string` and `Bytes`, then you must set the maximum parameter size so that OCCI can allocate the maximum size buffer:

```
Statement->setMaxParamSize(int parameterIndex, int maxParamSize);
```

You do not need to set the maximum parameter size for fixed length data types, such as `Number` and `Date`, or for parameters that use the `setDataBuffer()` method.

You can retrieve the current maximum parameter size setting by calling the `getMaxParamSize()` method.

### Executing an Iterative Operation

Once you have set the maximum number of iterations and (if necessary) the maximum parameter size, iterative execution using a parameterized statement is straightforward, as shown in the following example:

```
stmt->setSQL("INSERT INTO basket_tab VALUES(:1, :2)");

stmt->setString(1, "Apples"); // value for first parameter of first row
stmt->setInt(2, 6);          // value for second parameter of first row
stmt->addIteration();       // add the iteration

stmt->setString(1, "Oranges"); // value for first parameter of second row
stmt->setInt(2, 4);           // value for second parameter of second row
```

```
stmt->executeUpdate();           // execute statement
```

As shown in the example, you call the `addIteration()` method after each iteration except the last, after which you invoke `executeUpdate()` method. Of course, if you did not have a second row to insert, then you would not need to call the `addIteration()` method or make the subsequent calls to the `setxxx()` methods.

### INotes on Iterative Execution

- Iterative execution is designed only for use in `INSERT`, `UPDATE` and `DELETE` operations that use either standard or parameterized statements. It cannot be used for callable statements and queries.
- The data type cannot be changed between iterations. For example, if you use `setInt()` for parameter 1, then you cannot use `setString()` for the same parameter in a later iteration.

## Executing SQL Queries

SQL query statements allow your applications to request information from a database based on any constraints specified. A result set is returned as a result of a query.

### Using the Result Set

Execution of a database query puts the results of the query into a set of rows called the result set. In OCCI, a SQL `SELECT` statement is executed by the `executeQuery` method of the `Statement` class. This method returns an `ResultSet` object that represents the results of a query.

```
ResultSet *rs = stmt->executeQuery("SELECT * FROM basket_tab");
```

Once you have the data in the result set, you can perform operations on it. For example, suppose you wanted to print the contents of this table. The `next()` method of the `ResultSet` is used to fetch data, and the `getxxx()` methods are used to retrieve the individual columns of the result set, as shown in the following code example:

```
cout << "The basket has:" << endl;

while (rs->next())
{
    string fruit = rs->getString(1);    // get the first column as string
    int quantity = rs->getInt(2);      // get the second column as int

    cout << quantity << " " << fruit << endl;
}
```

The `next()` and `status()` methods of the `ResultSet` class return `Status`, as defined in [Table 13-37](#).

If data is available for the current row, then the status is `DATA_AVAILABLE`. After all the data has been read, the status changes to `END_OF_FETCH`. If there are any output streams to be read, then the status is `STREAM_DATA_AVAILABLE`, until all the streamed data are read successfully.

[Example 3-27](#) illustrates how to fetch streaming data into a result set, while section ["Streamed Reads and Writes"](#) on page 3-15 provides the general background.

**Example 3–27 How to Fetch Data in Streaming Mode Using ResultSet**

```

char buffer[4096];
ResultSet *rs = stmt->executeQuery
    ("SELECT col1, col2 FROM tab1 WHERE col1 = 11");
rs->setCharacterStreamMode(2, 10000);

while (rs->next ())
{
    unsigned int length = 0;
    unsigned int size = 500;
    Stream *stream = rs->getStream (2);
    while (stream->status () == Stream::READY_FOR_READ)
    {
        length += stream->readBuffer (buffer +length, size);
    }
    cout << "Read " << length << " bytes into the buffer" << endl;
}

```

**Specifying the Query**

The `IN` bind variables can be used with queries to specify constraints in the `WHERE` clause of a query. For example, the following program prints only those items that have a minimum quantity of 4:

```

stmt->setSQL("SELECT * FROM basket_tab WHERE quantity >= :1");
int minimumQuantity = 4;
stmt->setInt(1, minimumQuantity); // set first parameter
ResultSet *rs = stmt->executeQuery();
cout << "The basket has:" << endl;

while (rs->next())
    cout << rs->getInt(2) << " " << rs->getString(1) << endl;

```

**Optimizing Performance by Setting Prefetch Count**

Although the `ResultSet` method retrieves data one row at a time, the actual fetch of data from the server need not entail a network round-trip for each row queried. To maximize the performance, you can set the number of rows to prefetch in each round-trip to the server.

You effect this either by setting the number of rows to be prefetched through the `setPrefetchRowCount()` method, or by setting the memory size to be used for prefetching through the `setPrefetchMemorySize()` method.

If you set both of these attributes, then the specified number of rows are prefetched unless the specified memory limit is reached first. If the specified memory limit is reached first, then the prefetch returns as many rows as will fit in the memory space defined by the call to the `setPrefetchMemorySize()` method.

By default, prefetching is turned on, and the database fetches an extra row all the time. To turn prefetching off, set both the prefetch row count and memory size to 0.

---

**Note:** Prefetching is not in effect if `LONG` columns are part of the query. Queries containing `LOB` columns *can* be prefetched, because the `LOB` locator, rather than the data, is returned by the query.

---

## Executing Statements Dynamically

When you know that you need to execute a DML operation, you use the `executeUpdate` method. Similarly, when you know that you need to execute a query, you use `executeQuery()` method.

If your application needs to allow for dynamic events and you cannot be sure of which statement will need to be executed at run time, then OCCI provides the `execute()` method. Invoking the `execute()` method returns one of the following statuses:

- UNPREPARED
- PREPARED
- RESULT\_SET\_AVAILABLE
- UPDATE\_COUNT\_AVAILABLE
- NEEDS\_STREAM\_DATA
- STREAM\_DATA\_AVAILABLE

While invoking the `execute()` method will return one of these statuses, you can also interrogate the statement by using the `status` method.

```
Statement stmt = conn->createStatement();
Statement::Status status = stmt->status();           // status is UNPREPARED
stmt->setSQL("select * from emp");
status = stmt->status();                             // status is PREPARED
```

If a statement object is created with a SQL string, then it is created in a `PREPARED` state. For example:

```
Statement stmt = conn->createStatement("insert into foo(id) values(99)");
Statement::Status status = stmt->status(); // status is PREPARED
status = stmt->execute();                 // status is UPDATE_COUNT_AVAILABLE
```

When you set another SQL statement on the `Statement`, the status changes to `PREPARED`. For example:

```
stmt->setSQL("select * from emp");           // status is PREPARED
status = stmt->execute();                   // status is RESULT_SET_AVAILABLE
```

## Statement Status Definitions

This section describes the possible values of `Status` related to a statement object:

- UNPREPARED
- PREPARED
- RESULT\_SET\_AVAILABLE
- UPDATE\_COUNT\_AVAILABLE
- NEEDS\_STREAM\_DATA
- STREAM\_DATA\_AVAILABLE

### UNPREPARED

If you have not used the `setSQL()` method to attribute a SQL string to a statement object, then the statement is in an `UNPREPARED` state.

```
Statement stmt = conn->createStatement();
Statement::Status status = stmt->status(); // status is UNPREPARED
```

## PREPARED

If a Statement is created with an SQL string, then it is created in a PREPARED state. For example:

```
Statement stmt = conn->createStatement("INSERT INTO demo_tab(id) VALUES(99)");
Statement::Status status = stmt->status();    // status is PREPARED
```

Setting another SQL statement on the Statement will also change the status to PREPARED. For example:

```
status = stmt->execute();                    // status is UPDATE_COUNT_AVAILABLE
stmt->setSQL("SELECT * FROM demo_tab");      // status is PREPARED
```

## RESULT\_SET\_AVAILABLE

A status of RESULT\_SET\_AVAILABLE indicates that a properly formulated query has been executed and the results are accessible through a result set.

When you set a statement object to a query, it is PREPARED. Once you have executed the query, the statement changes to RESULT\_SET\_AVAILABLE. For example:

```
stmt->setSQL("SELECT * from EMP");           // status is PREPARED
status = stmt->execute();                    // status is RESULT_SET_AVAILABLE
```

To access the data in the result set, issue the following statement:

```
ResultSet *rs = Statement->getResultSet();
```

## UPDATE\_COUNT\_AVAILABLE

When a DDL or DML statement in a PREPARED state is executed, its state changes to UPDATE\_COUNT\_AVAILABLE, as shown in the following code example:

```
Statement stmt = conn->createStatement("INSERT INTO demo_tab(id) VALUES(99)");
Statement::Status status = stmt->status(); // status is PREPARED
status = stmt->execute();                  // status is UPDATE_COUNT_AVAILABLE
```

This status refers to the number of rows affected by the execution of the statement. It indicates that:

- The statement did not include any input or output streams.
- The statement was not a query but either a DDL or DML statement.

You can obtain the number of rows affected by issuing the following statement:

```
Statement->getUpdateCount();
```

Note that a DDL statement will result in an update count of zero (0). Similarly, an update that does not meet any matching conditions will also produce a count of zero (0). In such a case, you cannot infer the kind of statement that has been executed from the reported status.

## NEEDS\_STREAM\_DATA

If there are any output streams to be written, the execute does not complete until all the stream data is completely provided. In this case, the status changes to NEEDS\_STREAM\_DATA to indicate that a stream must be written. After writing the stream, call the `status()` method to find out if more stream data should be written, or whether the execution has completed.

In cases where your statement includes multiple streamed parameters, use the `getCurrentStreamParam()` method to discover which parameter needs to be written.

If you are performing an iterative or array execute, the `getCurrentStreamIteration()` method reveals to which iteration the data is to be written.

Once all the stream data has been processed, the status changes to either `RESULT_SET_AVAILABLE` or `UPDATE_COUNT_AVAILABLE`.

### **STREAM\_DATA\_AVAILABLE**

This status indicates that the application requires some stream data to be read in `OUT` or `IN/OUT` parameters before the execution can finish. After reading the stream, call the `status` method to find out if more stream data should be read, or whether the execution has completed.

In cases in which your statement includes multiple streamed parameters, use the `getCurrentStreamParam()` method to discover which parameter needs to be read.

If you are performing an iterative or array execute, then the `getCurrentStreamIteration()` method reveals from which iteration the data is to be read.

Once all the stream data has been handled, the status changes to `UPDATE_COUNT_REMOVE_AVAILABLE`.

The `ResultSet` class also has readable streams and it operates similar to the readable streams of the `Statement` class.

## **Committing a Transaction**

All SQL DML statements are executed in the context of a transaction. An application causes the changes made by these statement to become permanent by either committing the transaction, or undoing them by performing a rollback. While the SQL `COMMIT` and `ROLLBACK` statements can be executed with the `executeUpdate()` method, you can also call the `Connection::commit()` and `Connection::rollback()` methods.

If you want the DML changes that were made to be committed immediately, you can turn on the auto commit mode of the `Statement` class by issuing the following statement:

```
Statement::setAutoCommit(TRUE);
```

Once auto commit is in effect, each change is automatically made permanent. This is similar to issuing a commit right after each execution.

To return to the default mode, auto commit off, issue the following statement:

```
Statement::setAutoCommit(FALSE);
```

## **Caching Statements**

The statement caching feature establishes and manages a cache of statements within a session. It improves performance and scalability of application by efficiently using prepared cursors on the server side and eliminating repetitive statement parsing.

Statement caching can be used with connection and session pooling, and also without connection pooling. Please review [Example 3-28](#) and [Example 3-29](#) for typical usage scenarios.

**Example 3–28 Statement Caching without Connection Pooling**

These steps and accompanying pseudocode implement the statement caching feature without use of connection pools:

1. Create a `Connection` by making a `createConnection()` call on the `Environment` object.

```
Connection *conn = env->createConnection(  
    username, password, connecstr);
```

2. Enable statement caching on the `Connection` object by using a nonzero `size` parameter in the `setStmtCacheSize()` call.

```
conn->setStmtCacheSize(10);
```

Subsequent calls to `getStmtCacheSize()` would determine the size of the cache, while `setStmtCacheSize()` call changes the size of the statement cache, or disables statement caching if the `size` parameter is set to zero.

3. Create a `Statement` by making a `createStatement()` call on the `Connection` object; the `Statement` is returned if it is in the cache already, or a new `Statement` with a `NULL` tag is created for the user.

```
Statement *stmt = conn->createStatement(sql);
```

To retrieve a previously cached tagged statement, use the alternate form of the `createStatement()` method:

```
Statement *stmt = conn->createStatement(sql, tag);
```

4. Use the statement to execute SQL commands and obtain results.
5. Return the statement to cache.

```
conn->terminateStatement(stmt, tag);
```

If you don't want to cache this statement, use the `disableCaching()` call and an alternate form of `terminateStatement()`:

```
stmt->disableCaching();  
conn->terminateStatement(stmt);
```

If you need to verify whether a statement has been cached, issue an `isCached()` call on the `Connection` object.

You can choose to tag a statement at release time and then re-use it for another statement with the same tag. The tag will be used to search the cache. An untagged statement, where tag is `NULL`, is a special case of a tagged statement. Two statements are considered different if they only differ in their tags, and if only one of them is tagged.

6. Terminate the connection.

**Example 3–29 Statement Caching with Connection Pooling**

These steps and accompanying pseudocode implement the statement caching feature with connection pooling:

1. Create a `ConnectionPool` by making a call to the `createConnectionPool()` of the `Environment` object.

```
ConnectionPool *conPool = env->createConnectionPool(  
    username, password, connecstr,
```



```
minConn, maxConn, incrConn);
```

If using a `StatelessConnectionPool`, call `createStatelessConnectionPool()` instead. Subsequent operations are the same for `ConnectionPool` and `StatelessConnectionPool` objects.

```
Stateless ConnectionPool *conPool = env->createStatelessConnectionPool(
    username, password, connecstr,
    minConn, maxConn, incrConn, mode);
```

2. Enable statement caching for all Connections in the `ConnectionPool` by using a nonzero size parameter in the `setStmtCacheSize()` call.

```
conPool->setStmtCacheSize(10);
```

Subsequent calls to `getStmtCacheSize()` would determine the size of the cache, while `setStmtCacheSize()` call changes the size of the statement cache, or disables statement caching if the size parameter is set to zero.

3. Get a `Connection` from the pool by making a `createConnection()` call on the `ConnectionPool` object; the `Statement` is returned if it is in the cache already, or a new `Statement` with a NULL tag is created for the user.

```
Connection *conn = conPool->createConnection(username, password, connecstr);
```

To retrieve a previously cached tagged statement, use the alternate form of the `createStatement()` method:

```
Statement *stmt = conn->createStatement(sql, tag);
```

4. Create a `Statement` by making a `createStatement()` call on the `Connection` object; the `Statement` is returned if it is in the cache already, or a new `Statement` with a NULL tag is created for the user.

```
Statement *stmt = conn->createStatement(sql);
```

To retrieve a previously cached tagged statement, use the alternate form of the `createStatement()` method:

```
Statement *stmt = conn->createStatement(sql, tag);
```

5. Use the statement to execute SQL commands and obtain results.
6. Return the statement to cache.

```
conn->terminateStatement(stmt, tag);
```

If you don't want to cache this statement, use the `disableCaching()` call and an alternate form of `terminateStatement()`:

```
stmt->disableCaching();
conn->terminateStatement(stmt);
```

If you need to verify whether a statement has been cached, issue an `isCached()` call on the `Connection` object.

7. Release the connection `terminateConnection()`.

```
conPool->terminateConnection(conn);
```

---

**Note:**

- Statement caching is enabled only for connection created after the `setStmtCacheSize()` call.
  - If statement caching is not enabled at the pool level, it can still be implemented for individual connections in the pool.
- 

## Handling Exceptions

Each OCCI method is capable of generating an exception if it is not successful. This exception is of type `SQLException`. OCCI uses the C++ Standard Template Library (STL), so any exception that can be thrown by the STL can also be thrown by OCCI methods.

The STL exceptions are derived from the standard exception class. The `exception::what()` method returns a pointer to the error text. The error text is guaranteed to be valid during the catch block

The `SQLException` class contains Oracle specific error numbers and messages. It is derived from the standard exception class, so it too can obtain the error text by using the `exception::what()` method.

In addition, the `SQLException` class has two methods it can use to obtain error information. The `getErrorCode()` method returns the Oracle error number. The same error text returned by `exception::what()` can be obtained by the `getMessage()` method. The `getMessage()` method returns an STL string so that it can be copied like any other STL string.

Based on your error handling strategy, you may choose to handle OCCI exceptions differently from standard exceptions, or you may choose not to distinguish between the two.

If you decide that it is not important to distinguish between OCCI exceptions and standard exceptions, your catch block might look similar to the following:

```
catch (exception &excp)
{
    cerr << excp.what() << endl;
}
```

Should you decide to handle OCCI exceptions differently than standard exceptions, your catch block might look like the following:

```
catch (SQLException &sqlExcp)
{
    cerr <<sqlExcp.getErrorCode << ": " << sqlExcp.getErrorMessage() << endl;
}
catch (exception &excp)
{
    cerr << excp.what() << endl;
}
```

In the preceding catch block, SQL exceptions are caught by the first block and non-SQL exceptions are caught by the second block. If the order of these two blocks were to be reversed, SQL exceptions would never be caught. Since `SQLException` is derived from the standard exception, the standard exception catch block would handle the SQL exception as well.

**See Also:**

- Description of a special feature for handling errors that arise during batch updates, described in section "[Modifying Rows Iteratively](#)" on page 12-8 in [Chapter 12, "Optimizing Performance of OCCI Applications"](#)
- *Oracle Database Error Messages* for more information about Oracle error messages.

**Handling Null and Truncated Data**

In general, OCCI does not cause an exception when the data value retrieved by using the `getxxx()` methods of the `ResultSet` class or `Statement` class is `NULL` or truncated. However, this behavior can be changed by calling the `setErrorOnNull()` method or `setErrorOnTruncate()` method. If the `setErrorxxx()` methods are called with `causeException=TRUE`, then an `SQLException` is raised when a data value is `NULL` or truncated.

The default behavior is not to raise an `SQLException`. A column or parameter value can also be `NULL`, as determined by a call to `isNull()` for a `ResultSet` or `Statement` object returning `TRUE`:

```
rs->isNull(columnIndex);
stmt->isNull(paramIndex);
```

If the column or parameter value is truncated, it will also return `TRUE` as determined by a `isTruncated()` call on a `ResultSet` or `Statement` object:

```
rs->isTruncated(columnIndex);
stmt->isTruncated(paramIndex);
```

For data retrieved through the `setDataBuffer()` method and `setDataBufferArray()` method, exception handling behavior is controlled by the presence or absence of indicator variables and return code variables as shown in [Table 3-1](#), [Table 3-2](#), and [Table 3-3](#).

**Table 3-1 Normal Data - Not Null and Not Truncated**

Return Code	Indicator - not provided	Indicator - provided
Not provided	error = 0	error = 0 indicator = 0
Provided	error = 0 return code = 0	error = 0 indicator = 0 return code = 0

**Table 3-2 Null Data**

Return Code	Indicator - not provided	Indicator - provided
Not provided	<code>SQLException</code> error = 1405	error = 0 indicator = -1
Provided	<code>SQLException</code> error = 1405 return code = 1405	error = 0 indicator = -1 return code = 1405

**Table 3–3 Truncated Data**

<b>Return Code</b>	<b>Indicator - not provided</b>	<b>Indicator - provided</b>
<b>Not provided</b>	SQLException error = 1406	SQLException error = 1406 indicator = data_len
<b>Provided</b>	error = 24345 return code = 1405	error = 24345 indicator = data_len return code = 1406

In [Table 3–3](#), `data_len` is the actual length of the data that has been truncated if this length is less than or equal to `SB2MAXVAL`. Otherwise, the indicator is set to `-2`.

---

---

## Object Programming

This chapter provides information on how to implement object-relational programming using the Oracle C++ Call Interface (OCCI).

This chapter contains these topics:

- [Overview of Object Programming](#)
- [Working with Objects in OCCI](#)
- [Representing Objects in C++ Applications](#)
- [Developing an OCCI Object Application](#)
- [Migrating C++ Applications Using OCCI](#)
- [Overview of Associative Access](#)
- [Overview of Navigational Access](#)
- [Overview of Complex Object Retrieval](#)
- [Working with Collections](#)
- [Using Object References](#)
- [Deleting Objects from the Database](#)
- [Type Inheritance](#)
- [A Sample OCCI Application](#)

### Overview of Object Programming

OCCI supports both the associative and navigational style of data access. Traditionally, third-generation language (3GL) programs manipulate data stored in a database by using the **associative access** based on the associations organized by relational database tables. In associative access, data is manipulated by executing SQL statements and PL/SQL procedures. OCCI supports associative access to objects by enabling your applications to execute SQL statements and PL/SQL procedures on the database server without incurring the cost of transporting data to the client.

Object-oriented programs that use OCCI can also make use of **navigational access** that is a key aspect of this programming paradigm. Object relationships between objects are implemented as references (REFs). Typically, an object application that uses navigational access first retrieves one or more objects from the database server by issuing a SQL statement that returns REFs to those objects. The application then uses those REFs to traverse related objects, and perform computations on these other objects as required. Navigational access does not involve executing SQL statements, except to fetch the references of an initial set of objects. By using the OCCI APIs for

navigational access, your application can perform the following functions on Oracle objects:

- Creating, accessing, locking, deleting, copying and flushing objects
- Getting references to objects and navigating through the references

This chapter gives examples that show you how to create a persistent object, access an object, modify an object, and flush the changes to the database server. It discusses how to access the object using both navigational and associative approaches.

## Working with Objects in OCCI

Many of the programming principles that govern a relational OCCI applications are identical for object-relational applications. An object-relational application uses the standard OCCI calls to establish database connections and process SQL statements. The difference is that the SQL statements that are issued retrieve object references, which can then be manipulated with OCCI object functions. An object can also be directly manipulated as a value (without using its object reference).

Instances of an Oracle type are categorized into **persistent objects** and **transient objects** based on their lifetime. Instances of persistent objects can be further divided into **standalone objects** and **embedded objects** depending on whether or not they are referenced by way of an object identifier.

### Persistent Objects

A **persistent object** is an object which is stored in an Oracle database. It may be fetched into the object cache and modified by an OCCI application. The lifetime of a persistent object can exceed that of the application which is accessing it. There are two types of persistent objects:

- A **standalone instance** is stored in a database table row, and has a unique object identifier. An OCCI application can retrieve a reference to a standalone object, pin the object, and navigate from the pinned object to other related objects. Standalone objects may also be referred to as **referenceable objects**.

It is also possible to select a persistent object, in which case you fetch the object *by value* instead of fetching it by reference.

- An **embedded instance** is not stored in a database table row, but rather is embedded within another object. Examples of embedded objects are objects which are attributes of another object, or objects that exist in an object column of a database table. Embedded objects do not have object identifiers, and OCCI applications cannot get REFs to embedded instances.

Embedded objects may also be referred to as **nonreferenceable objects** or **value instances**. You may sometimes see them referred to as **values**, which is not to be confused with scalar data values. The context should make the meaning clear.

---

---

**Note:**

- Users don't have to explicitly delete persistent objects that have been materialized through references.
  - Users should delete persistent objects created by application when the transactions are rolled back
- 
-

The following SQL examples demonstrate the difference between these two types of persistent objects.

#### **Example 4-1 Creating Standalone Objects**

This code example demonstrates how a standalone object is created:

```
CREATE TYPE person_t AS OBJECT
  (name      varchar2(30),
   age       number(3));
CREATE TABLE person_tab OF person_t;
```

Objects that are stored in the object table `person_tab` are standalone objects. They have object identifiers and can be referenced. They can be pinned in an OCCl application.

#### **Example 4-2 Creating Embedded Objects**

This code example demonstrates how an embedded object is created:

```
CREATE TABLE department
  (deptno    number,
   deptname  varchar2(30),
   manager   person_t);
```

Objects which are stored in the `manager` column of the `department` table are embedded objects. They do not have object identifiers, and they cannot be referenced. This means they cannot be pinned in an OCCl application, and they also never need to be unpinned. They are always retrieved into the object cache *by value*.

The Array Pin feature allows a vector of references to be dereferenced in one round-trip to return a vector of the corresponding objects. A new global method, `pinVectorOfRefs()`, takes a vector of `Refs` and populates a vector of `PObjects` in a single round-trip, saving the cost of pinning  $n-1$  references in  $n-1$  round-trips.

## Transient Objects

A transient object is an instance of an object type. Its lifetime cannot exceed that of the application. The application can also delete a transient object at any time.

The Object Type Translator (OTT) utility generates two `operator new` methods for each C++ class, as demonstrated in [Two methods for operator new in the Object Type Translator Utility](#) [Example 4-3](#):

#### **Example 4-3 Two methods for operator new in the Object Type Translator Utility**

```
class Person : public PObject {
  ...
public:
  dvoid *operator new(size_t size); // creates transient instance
  dvoid *operator new(size_t size, Connection &conn, string table);
                                     // creates persistent instance
}
```

[Example 4-4](#) demonstrates how to dynamically create a transient object. Transient objects cannot be converted to persistent objects. Their role is fixed at the time they are instantiated, and it is your responsibility to free memory by deleting transient objects.

**Example 4–4 How to Dynamically Create a Transient Object**

```
Person *p = new Person();
```

A transient object can also be created on the stack as a local variable, as demonstrated in [Example 4–5](#). The latter approach guarantees that the transient object is destroyed when the scope of the variable ends.

**Example 4–5 How to Create a Transient Object as a Local Variable**

```
Person p;
```

**See Also:**

- *Oracle Database Concepts* for more information about objects

## Values

In the context of this manual, a **value** refers to either:

- A scalar value which is stored in a non-object column of a database table. An OCI application can fetch values from a database by issuing SQL statements.
- An embedded (nonreferenceable) object.

The context should make it clear which meaning is intended.

---

---

**Note:** It is possible to `SELECT` a referenceable object into the object cache, rather than pinning it, in which case you fetch the object *by value* instead of fetching it by reference.

---

---

## Representing Objects in C++ Applications

Before an OCI application can work with object types, those types must exist in the database. Typically, you create types with SQL DDL statements, such as `CREATE TYPE`.

### Creating Persistent and Transient Objects

The following sections discuss how persistent and transient objects are created.

**Example 4–6 Creating a Persistent Object**

Before you create a persistent object, you must have created the environment and opened a connection. The following example shows how to create a persistent object, `addr`, in the database table, `addr_tab`, created by means of a SQL statement:

```
CREATE TYPE ADDRESS AS OBJECT (  
    state CHAR(2),  
    zip_code CHAR(5));  
CREATE TABLE ADDR_TAB OF ADDRESS;  
ADDRESS *addr = new(conn, "ADDR_TAB") ADDRESS("CA", "94065");
```

The persistent object is created in the database only when one of the following occurs:

- The transaction is committed (`Connection::commit()`)
- The object cache is flushed (`Connection::flushCache()`)
- The object itself is flushed (`PObject::flush()`)



**Example 4-7 Creating a Transient Object**

An instance of the transient object ADDRESS is created in the following manner:

```
ADDRESS *addr_trans = new ADDRESS("MD", "94111");
```

**Creating Object Representations using the OTT Utility**

When your C++ application retrieves instances of object types from the database, it needs to have a client-side representation of the objects. The Object Type Translator (OTT) utility generates C++ class representations of database object types for you. For example, consider the following declaration of a type in your database:

```
CREATE TYPE address AS OBJECT (state CHAR(2), zip_code CHAR(5));
```

The OTT utility produces the following C++ class:

```
class ADDRESS : public PObject {

protected:
    string state;
    string zip;

public:
    void *operator new(size_t size);
    void *operator new(size_t size,
        const Connection* conn,
        const string& table);
    string getSQLTypeName() const;
    void getSQLTypeName(oracle::occi::Environment *env, void **schemaName,
        unsigned int &schemaNameLen, void **typeName,
        unsigned int &typeNameLen) const;
    ADDRESS(void *ctx) : PObject(ctx) { };
    static void *readSQL(void *ctx);
    virtual void readSQL(AnyData& stream);
    static void writeSQL(void *obj, void *ctx);
    virtual void writeSQL(AnyData& stream);
}
```

These class declarations are automatically written by OTT to a header (.h) file that you name. This header file is included in the source files for an application to provide access to objects. Instances of a PObject (as well as instances of classes derived from PObjects) can be either transient or persistent. The methods writeSQL() and readSQL() are used internally by the OCCI object cache to linearize and delinearize the objects and are not to be used or modified by OCCI clients.

**See Also:** [Chapter 8, "Object Type Translator Utility"](#) for more information about the OTT utility

**Developing an OCCI Object Application**

This section discusses the steps involved in developing a basic OCCI object application.

**Basic Object Program Structure**

The basic structure of an OCCI application that uses objects is similar to a relational OCCI application, the difference being object functionality. The steps involved in an OCCI object program include:


1. Initialize the `Environment`. Initialize the OCCI programming environment in object mode. Your application will most likely need to include C++ class representations of database objects in a header file. You can create these classes by using the Object Type Translator (OTT) utility, as described in [Chapter 8, "Object Type Translator Utility"](#).
2. Establish a Connection. Use the environment handle to establish a connection to the database server.
3. Prepare a SQL statement. This is a local (client-side) step, which may include binding placeholders. In an object-relational application, this SQL statement should return a reference (`REF`) to an object.
4. Access the object.
  - a. Associate the prepared statement with a database server, and execute the statement.
  - b. By using navigational access, retrieve an object reference (`REF`) from the database server and pin the object. You can then perform some or all of the following:
    - Manipulate the attributes of an object and mark it as **dirty** (modified)
    - Follow a reference to another object or series of objects
    - Access type and attribute information
    - Navigate a complex object retrieval graph
    - Flush modified objects to the database server
  - c. By using associative access, you can fetch an entire object *by value* by using SQL. Alternately, you can select an embedded (nonreferenceable) object. You can then perform some or all of the following:
    - Insert values into a table
    - Modify existing values
5. Commit the transaction. This step implicitly writes all modified objects to the database server and commits the changes.
6. Free statements and handles; the prepared statements should not be used or executed again.

**See Also:**

- [Chapter 3, "Relational Programming"](#) for information about using OCCI to connect to a database server, process SQL statements, and allocate handles
- [Chapter 8, "Object Type Translator Utility"](#) for information about the OTT utility
- [Chapter 13, "OCCI Application Programming Interface"](#) for descriptions of OCCI relational functions and the `Connect` class and the `getMetaData()` method

## Basic Object Operational Flow

Figure 3-1 shows a simple program logic flow for how an application might work with objects. For simplicity, some required steps are omitted.

**Figure 4-1 Basic Object Operational Flow**

The steps shown in Figure 3-1 are discussed in the following sections:

### Initialize OCCI in Object Mode

If your OCCI application accesses and manipulates objects, then it is essential that you specify a value of `OBJECT` for the mode parameter of the `createEnvironment()` method, the first call in any OCCI application. Specifying this value for mode indicates to OCCI that your application will be working with objects. This notification has the following important effects:

- The object run-time environment is established
- The object cache is set up

---

**Note:** If the mode parameter is not set to `OBJECT`, any attempt to use an object-related function will result in an error.

---

The following code example demonstrates how to specify the `OBJECT` mode when creating an OCCI environment:

```

Environment *env;
Connection *con;
Statement *stmt;

env = Environment::createEnvironment(Environment::OBJECT);
con = env->createConnection(userName, password, connectString);
  
```

Your application does not have to allocate memory when database objects are loaded into the object cache. The object cache provides transparent and efficient memory management for database objects. When database objects are loaded into the object cache, they are transparently mapped into the host language (C++) representation.

The object cache maintains the association between the object copy in the object cache and the corresponding database object. Upon `commit`, changes made to the object copy in the object cache are automatically propagated back to the database.

The object cache maintains a look-up table for mapping references to objects. When an application dereferences a reference to an object and the corresponding object is not yet cached in the object cache, the object cache automatically sends a request to the database server to fetch the object from the database and load it into the object cache. Subsequent dereferences of the same reference are faster since they are to the object cache itself and do not incur a round-trip to the database server.

Subsequent dereferences of the same reference fetch from the cache instead of requiring a round-trip. The exception to this is in the case of a dereferencing operation that occurs just after a commit. In this case, the latest object copy from the server is returned. This ensures that the latest object from the database is cached after each transaction.

The object cache maintains a pin count for each persistent object in the object cache. When an application dereferences a reference to an object, the pin count of the object is incremented. The subsequent dereferencing of the same reference to the object does not change the pin count. Until the reference to the object goes out of scope, the object will continue to be pinned in the object cache and be accessible by the OCCI client.

The pin count functions as a reference count for the object. The pin count of the object becomes zero (0) only when there are no more references referring to this object, during which time the object becomes eligible for garbage collection. The object cache uses a least recently used algorithm to manage the size of the object cache. This algorithm frees objects with a pin count of 0 when the object cache reaches the maximum size.

### **Pin Object**

In most situations, OCCI users do not need to explicitly pin or unpin the objects because the object cache automatically keeps track of the pin counts of all the objects in the cache. As explained earlier, the object cache increments the pin count when a reference points to the object and decrements it when the reference goes out of scope or no longer points to the object.

But there is one exception. If an OCCI application uses `Ref<T>::ptr()` method to get a pointer to the object, then the `pin` and `unpin` methods of the `PObject` class can be used by the application to control pinning and unpinning of the objects in the object cache.

### **Operate on Object in Cache**

Note that the object cache does not manage the contents of object copies; it does not automatically refresh object copies. Your application must ensure the validity and consistency of object copies.

### **Flush Changes to Object**

Whenever changes are made to object copies in the object cache, your application is responsible for flushing the changed object to the database.

Memory for the object cache is allocated on demand when objects are loaded into the object cache.

The client-side object cache is allocated in the program's process space. This object cache is the memory for objects that have been retrieved from the database server and are available to your application.

---

---

**Note:** If you initialize the OCCI environment in object mode, your application allocates memory for the object cache, whether or not the application actually uses object calls.

---

---

There is only one object cache allocated for each OCCI environment. All objects retrieved or created through different connections within the environment use the same physical object cache. Each connection has its own logical object cache.

### Deletion of an Object

For objects retrieved into the cache by dereferencing a reference, you should not perform an explicit delete. For such objects, the pin count is incremented when a reference is dereferenced for the first time and decremented when the reference goes out of scope. When the pin count of the object becomes 0, indicating that all references to that object are out of scope, the object is automatically eligible for garbage collection and subsequently deleted from the cache.

For persistent objects that have been created by calling the `new` operator, you must call a `delete` if you do not commit the transaction. Otherwise, the object is garbage collected after the commit. This is because when such an object is created using `new`, its pin count is initially 0. However, because the object is dirty it remains in the cache. After a commit, it is no longer dirty and thus garbage collected. Therefore, a `delete` is not required.

If a commit is not performed, then you must explicitly call `delete` to destroy that object. You can do this as long as there are no references to that object. For transient objects, you must delete explicitly to destroy the object.

You should not call a `delete` operator on a persistent object. A persistent object that is not marked/dirty is freed by the garbage collector when its pin count is 0. However, for transient objects you must delete explicitly to destroy the object.

## Migrating C++ Applications Using OCCI

This section will describe how to migrate existing C++ applications using OCCI.

### Steps for Migration

- Determine object model and class hierarchy
- Use JDeveloper9i to map to Oracle object schema
- Generate C++ header files using Oracle Type Translator
- Modify old C++ access classes as required to work with new object type definitions
- Add functionality for transient and persistent object management, as required.

## Overview of Associative Access

You can employ SQL within OCCI to retrieve objects, and to perform DML operations:

- [Using SQL to Access Objects](#)
- [Inserting and Modifying Values](#)

**See Also:** complete code listing of the demonstration programs

## Using SQL to Access Objects

In the previous sections we discussed navigational access, where SQL is used only to fetch the references of an initial set of objects and then navigate from them to the other objects. Here we will discuss how to fetch the objects using SQL.

The following example shows how to use the `ResultSet::getObject()` method to fetch objects through associative access where it gets each object from the table, `addr_tab`, using SQL:

```
string sel_addr_val = "SELECT VALUE(address) FROM ADDR_TAB address";

ResultSet *rs = stmt->executeQuery(sel_addr_val);

while (rs->next())
{
    ADDRESS *addr_val = rs->getObject(1);
    cout << "state: " << addr_val->getState();
}
```

The objects fetched through associative access are termed value instances and they behave just like transient objects. Methods such as `markModified()`, `flush()`, and `markDeleted()` are applicable only for persistent objects.

Any changes made to these objects are not reflected in the database.

Since the object returned is a value instance, it is the user's responsibility to free memory by deleting the object pointer.

## Inserting and Modifying Values

We have just seen how to use SQL to access objects. OCCI also provides the ability to use SQL to insert new objects or modify existing objects in the database server through the `Statement::setObject` method interface.

The following example creates a transient object `Address` and inserts it into the database table `addr_tab`:

```
ADDRESS *addr_val = new address("NV", "12563"); // new a transient instance
stmt->setSQL("INSERT INTO ADDR_TAB values(:1)");
stmt->setObject(1, addr_val);
stmt->execute();
```

## Overview of Navigational Access

By using navigational access, you engage in a series of operations:

- [Retrieving an Object Reference \(REF\) from the Database Server](#)
- [Pinning an Object](#)
- [Manipulating Object Attributes](#)
- [Marking Objects and Flushing Changes](#)

**See Also:** complete code listing of the demonstration programs

### Retrieving an Object Reference (REF) from the Database Server

In order to work with objects, your application must first retrieve one or more objects from the database server. You accomplish this by issuing a SQL statement that returns references (REFs) to one or more objects.

---



---

**Note:** It is also possible for a SQL statement to fetch value instances, rather than REFs, from a database.

---



---

The following SQL statement retrieves a REF to a single object address from the database table `addr_tab`:

```
string sel_addr = "SELECT REF(address)
  FROM addr_tab address
  WHERE zip_code = '94065'";
```

The following code example illustrates how to execute the query and fetch the REF from the result set.

```
ResultSet *rs = stmt->executeQuery(sel_addr);
rs->next();
Ref<address> addr_ref = rs->getRef(1);
```

At this point, you could use the object reference to access and manipulate the object or objects from the database.

**See Also:** ["Executing SQL DDL and DML Statements"](#) on page 3-11 for general information about preparing and executing SQL statements

## Pinning an Object

Upon completion of the fetch step, your application has a REF to an object. The actual object is not currently available to work with. Before you can manipulate an object, it must be **pinned**. Pinning an object loads the object into the object cache, and enables you to access and modify the object's attributes and follow references from that object to other objects. Your application also controls when modified objects are written back to the database server.

---



---

**Note:** This section deals with a simple pin operation involving a single object at a time. For information about retrieving multiple objects through complex object retrieval, see the section [Overview of Complex Object Retrieval](#) on page 4-14.

---



---

OCCI requires only that you dereference the REF in the same way you would dereference any C++ pointer. Dereferencing the REF transparently materializes the object as a C++ class instance.

Continuing the `Address` class example from the previous section, assume that the user has added the following method:

```
string Address::getState()
{
    return state;
}
```

To dereference this REF and access the object's attributes and methods:

```
string state = addr_ref->getState();    // -> pins the object
```

The first time `Ref<T> (addr_ref)` is dereferenced, the object is pinned, which is to say that it is loaded into the object cache from the database server. From then on, the

behavior of operator `->` on `Ref<T>` is just like that of any C++ pointer (`T *`). The object remains in the object cache until the `REF (addr_ref)` goes out of scope. It then becomes eligible for garbage collection.

Now that the object has been pinned, your application can modify that object.

## Manipulating Object Attributes

Manipulating object attributes is no different from that of accessing them as shown in the previous section. Let us assume the `Address` class has the following user defined method that sets the `state` attribute to the input value:

```
void Address::setState(string new_state)
{
    state = new_state;
}
```

The following example shows how to modify the state attribute of the object, `addr`:

```
addr_ref->setState("PA");
```

As explained earlier, the first invocation of the operator `->` on `Ref<T>` loads the object if not already in the object cache.

## Marking Objects and Flushing Changes

In the example in the previous section, an attribute of an object was changed. At this point, however, that change exists only in the client-side cache. The application must take specific steps to ensure that the change is written to the database.

### Marking an Object as Modified (Dirty)

The first step is to indicate that the object has been modified. This is done by calling the `markModified()` method on the object (derived method of `PObject`). This method marks the object as **dirty** (modified).

Continuing the previous example, after object attributes are manipulated, the object referred to by `addr_ref` can be marked dirty as follows:

```
addr_ref->markModified();
```

## Recording Changes in the Database

Objects that have had their dirty flag set must be flushed to the database server for the changes to be recorded in the database. This can be done in three ways:

- Flush a single object marked dirty by calling the method `flush`, a derived method of `PObject`.
- Flush the entire object cache using the `Connection::flushCache()` method. In this case, `OCCI` traverses the dirty list maintained by the object cache and flushes all the dirty objects.
- Commit a transaction by calling the `Connection::commit()` method. Doing so also traverses the dirty list and flushes the objects to the database server. The dirty list includes newly created persistent objects.

## Garbage Collection in the Object Cache

The object cache has two important associated parameters:



- The maximum cache size percentage
- The optimal cache size

These parameters refer to levels of cache memory usage, and they help to determine when the cache automatically "ages out" eligible objects to free up memory.

If the memory occupied by the objects currently in the cache reaches or exceeds the maximum cache size, the cache automatically begins to free (or age out) unmarked objects which have a pin count of zero. The cache continues freeing such objects until memory usage in the cache reaches the optimal size, or until it runs out of objects eligible for freeing.

---



---

**Note:** The cache can grow beyond the specified maximum cache size.

---



---

The maximum object cache size (in bytes) is computed by incrementing the optimal cache size (`optimal_size`) by the maximum cache size percentage (`max_size_percentage`), as follows:

```
Maximum cache size = optimal_size + optimal_size * max_size_percentage / 100;
```

The default value for the maximum cache size percentage is 10%. The default value for the optimal cache size is 8MB. When a persistent object is created through the overloaded `PObject::new()` operator, the newly created object is marked dirty and its pin count is set to 0.

These parameters can be set or retrieved using the following member functions of the `Environment` class:

- `void setCacheMaxSize(unsigned int maxSize);`
- `unsigned int getCacheMaxSize() const;`
- `void setCacheOptSize(unsigned int OptSize);`
- `unsigned int getCacheOptSize() const;`

"Pin Object" on page 4-8 describes how pin count of an object functions as a reference count and how an unmarked object with a 0 pin count can become eligible for garbage collection. In the case of a newly created persistent object, the object is unmarked after the transaction is committed or aborted and if the object has a 0 pin count, in other words there are no references referring to it. The object then becomes a candidate for being aged out.

If you are working with several object that have a large number of string or collection attributes, most of the memory is allocated from the C++ heap; this is because OCCI uses STLs. You should therefore set the cache size to a low value to avoid high memory use before garbage collection activates.

**See Also:** [Chapter 13, "OCCI Application Programming Interface"](#) for details.

## Transactional Consistency of References

As described in the previous section, dereferencing a `Ref<T>` for the first time results in the object being loaded into the object cache from the database server. From then on, the behavior of operator `->` on `Ref<T>` is the same as any C++ pointer and it provides access to the object copy in the cache. But once the transaction commits or aborts, the object copy in the cache can no longer be valid because it could be modified by any

other client. Therefore, after the transaction ends, when the `Ref<T>` is again dereferenced, the object cache recognizes the fact that the object is no longer valid and fetches the most recent copy from the database server.

## Overview of Complex Object Retrieval

In the examples discussed earlier, only a single object was fetched or pinned at a time. In these cases, each pin operation involved a separate database server round-trip to retrieve the object.

Object-oriented applications often model their problems as a set of interrelated objects that form graphs of objects. These applications process objects by starting with some initial set of objects and then using the references in these objects to traverse the remaining objects. In a client/server setting, each of these traversals could result in costly network round-trips to fetch objects.

The performance of such applications can be increased through the use of **complex object retrieval** (COR). This is a prefetching mechanism in which an application specifies some criteria (content and boundary) for retrieving a set of linked objects in a single network round-trip.

---

---

**Note:** Using COR does not mean that these prefetched objects are pinned. They are fetched into the object cache, so that subsequent pin calls are local operations.

---

---

A **complex object** is a set of logically related objects consisting of a root object, and a set of objects each of which is prefetched based on a given depth level. The **root** object is explicitly fetched or pinned. The **depth level** is the shortest number of references that need to be traversed from the root object to a given prefetched object in a complex object.

An application specifies a complex object by describing its content and boundary. The fetching of complex objects is constrained by an environment's **prefetch limit**, the amount of memory in the object cache that is available for prefetching objects.

---

---

**Note:** The use of complex object retrieval does not add functionality; it only improves performance, and so its use is optional.

---

---

## Retrieving Complex Objects

An OCCI application can achieve COR by setting the appropriate attributes of a `Ref<T>` before dereferencing it using the following methods:

```
// prefetch attributes of the specified type name up to the specified depth
Ref<T>::setPrefetch(const string &typeName, unsigned int depth);
// prefetch all the attribute types up to the specified depth.
Ref<T>::setPrefetch(unsigned int depth);
```

The application can also choose to fetch all objects reachable from the root object by way of REFS (transitive closure) to a certain depth. To do so, set the level parameter to the depth desired. For the preceding two examples, the application could also specify `(PO object REF, OCCI_MAX_PREFETCH_DEPTH)` and `(PO object REF, 1)` respectively to prefetch required objects. Doing so results in many extraneous fetches but is quite simple to specify, and requires only one database server round-trip.

As an example for this discussion, consider the following type declaration:

```
CREATE TYPE customer(...);
CREATE TYPE line_item(...);
CREATE TYPE line_item_varray as VARRAY(100) of REF line_item;
CREATE TYPE purchase_order AS OBJECT
  ( po_number      NUMBER,
    cust           REF customer,
    related_orders REF purchase_order,
    line_items     line_item_varray);
```

The `purchase_order` type contains a scalar value for `po_number`, a `VARRAY` of `line_items`, and two references. The first is to a `customer` type and the second is to a `purchase_order` type, indicating that this type can be implemented as a linked list.

When fetching a complex object, an application must specify the following:

- A reference to the desired root object
- One or more pairs of type and depth information to specify the boundaries of the complex object. The type information indicates which `REF` attributes should be followed for `COR`, and the depth level indicates how many levels deep those links should be followed.

In the case of the `purchase_order` object in the preceding example, the application must specify the following:

- The reference to the root `purchase_order` object
- One or more pairs of type and depth information for `customer`, `purchase_order`, or `line_item`

An application prefetching a purchase order will very likely need access to the customer information for that purchase order. Using simple navigation, this would require two database server accesses to retrieve the two objects.

Through complex object retrieval, `customer` can be prefetched when the application pins the `purchase_order` object. In this case, the complex object would consist of the `purchase_order` object and the `customer` object it references.

In the previous example, if the application wanted to prefetch a purchase order and the related customer information, the application would specify the `purchase_order` object and indicate that `customer` should be followed to a depth level of one as follows:

```
Ref<PURCHASE_ORDER> poref;
poref.setPrefetch("CUSTOMER", 1);
```

If the application wanted to prefetch a purchase order and all objects in the object graph it contains, the application would specify the `purchase_order` object and indicate that both `customer` and `purchase_order` should be followed to the maximum depth level possible as follows:

```
Ref<PURCHASE_ORDER> poref;
poref.setPrefetch("CUSTOMER", OCCI_MAX_PREFETCH_DEPTH);
poref.setPrefetch("PURCHASE_ORDER", OCCI_MAX_PREFETCH_DEPTH);
```

where `OCCI_MAX_PREFETCH_DEPTH` specifies that all objects of the specified type reachable through references from the root object should be prefetched.

If an application wanted to prefetch a purchase order and all the line items associated with it, the application would specify the `purchase_order` object and indicate that `line_items` should be followed to the maximum depth level possible as follows:

```
Ref<PURCHASE_ORDER> poref;  
poref.setPrefetch("LINE_ITEM", 1);
```

## Prefetching Complex Objects

After specifying and fetching a complex object, subsequent fetches of objects contained in the complex object do not incur the cost of a network round-trip, because these objects have already been prefetched and are in the object cache. Keep in mind that excessive prefetching of objects can lead to a flooding of the object cache. This flooding, in turn, may force out other objects that the application had already pinned leading to a performance degradation instead of performance improvement.

---

---

**Note:** If there is insufficient memory in the object cache to hold all prefetched objects, some objects may not be prefetched. The application will then incur a network round-trip when those objects are accessed later.

---

---

The `SELECT` privilege is needed for all prefetched objects. Objects in the complex object for which the application does not have `SELECT` privilege will not be prefetched.

An entire vector of `Refs` can be prefetched into object cache in a single round-trip by using the global `pinVectorOfRefs()` method of the [Connection Class](#). This method reduces the number of round-trips for an `n`-sized vector of `Refs` from `n` to `1`, and tracks the newly pinned objects through an `OUT` parameter vector.

## Working with Collections

Oracle supports two kinds of collections - variable length arrays (ordered collections) and nested tables (unordered collections). OCI maps both of them to a Standard Template Library (STL) vector container, giving you the full power, flexibility, and speed of an STL vector to access and manipulate the collection elements. The following is the SQL DDL to create a `VARRAY` and an object that contains an attribute of type `VARRAY`.

```
CREATE TYPE ADDR_LIST AS VARRAY(3) OF REF ADDRESS;  
CREATE TYPE PERSON AS OBJECT (name VARCHAR2(20), addr_1 ADDR_LIST);
```

Here is the C++ class declaration generated by OTT:

```
class PERSON : public PObject  
{  
protected:  
    string name;  
    vector< Ref< ADDRESS > > addr_1;  
  
public:  
    void *operator new(size_t size);  
    void *operator new(size_t size,  
        const Connection* conn,  
        const string& table);  
    string getSQLTypeName() const;  
    void getSQLTypeName(oracle::occi::Environment *env, void **schemaName,
```

```

        unsigned int &schemaNameLen, void **typeName,
        unsigned int &typeNameLen) const;
PERSON (void *ctx) : PObject(ctx) { };
static void *readSQL(void *ctx);
virtual void readSQL(AnyData& stream);
static void writeSQL(void *obj, void *ctx);
virtual void writeSQL(AnyData& stream);
}

```

**See Also:** complete code listing of the demonstration programs

## Fetching Embedded Objects

If your application needs to fetch an embedded object, which is an object stored in a column of a regular table rather than an object table, you cannot use the REF retrieval mechanism. Embedded instances do not have object identifiers, so it is not possible to get a reference to them. This means that they cannot serve as the basis for object navigation. There are still many situations, however, in which an application will want to fetch embedded instances.

For example, assume that an `address` type has been created.

```

CREATE TYPE address AS OBJECT
(
  street1      varchar2(50),
  street2      varchar2(50),
  city         varchar2(30),
  state        char(2),
  zip          number(5);

```

You could then use that type as the data type of a column in another table:

```

CREATE TABLE clients
(
  name      varchar2(40),
  addr      address);

```

Your OCCI application could then issue the following SQL statement:

```

SELECT addr FROM clients
WHERE name='BEAR BYTE DATA MANAGEMENT';

```

This statement would return an embedded `address` object from the `clients` table. The application could then use the values in the attributes of this object for other processing. The application should execute the statement and fetch the object in the same way as described in the section "[Overview of Associative Access](#)" on page 4-9.

## Nullness

If a column in a row of a database table has no value, then that column is said to be `NULL`, or to contain a `NULL`. Two different types of `NULL`s can apply to objects:

- Any attribute of an object can have a `NULL` value. This indicates that the value of that attribute of the object is not known.
- An object may be **atomically NULL**. This means that the value of the entire object is unknown.

Atomic `NULL`ness is not the same thing as nonexistence. An atomically `NULL` object still exists, its value is just not known. It may be thought of as an existing object with no data.

For every type of object attribute, OCCI provides a corresponding class. For instance, NUMBER attribute type maps to the `Number` class, REF maps to `RefAny`, and so on. Each and every OCCI class that represents a data type provides two methods:

- `isNull()` — returns whether the object is NULL
- `setNull()` — sets the object to NULL

Similarly, these methods are inherited from the `PObject` class by all the objects and can be used to access and set atomically NULL information about them.

## Using Object References

OCCI provides the application with the flexibility to access the contents of the objects using their pointers or their references. OCCI provides the `PObject::getRef()` method to return a reference to a persistent object. This call is valid for persistent objects only.

## Deleting Objects from the Database

OCCI users can use the overloaded `PObject::operator new()` to create the persistent objects. However, to delete the object from the database server, it is best to call `ref.markDelete()` directly on the `Ref`; this will prevent the object from getting into the client cache. If the object is in the client cache already, it can be removed by an `obj.markDelete()` call on the object. The object marked for deletion is permanently removed once the transaction commits.

## Type Inheritance

Type inheritance of objects has many similarities to inheritance in C++ and Java. You can create an object type as a subtype of an existing object type. The subtype is said to inherit all the attributes and methods (member functions and procedures) of the supertype, which is the original type. Only single inheritance is supported; an object cannot have more than one supertype. The subtype can add new attributes and methods to the ones it inherits. It can also override (redefine the implementation) of any of its inherited methods. A subtype is said to extend (that is, inherit from) its supertype.

**See Also:** *Oracle Database Object-Relational Developer's Guide* for a more complete discussion of this topic

As an example, a type `Person_t` can have a subtype `Student_t` and a subtype `Employee_t`. In turn, `Student_t` can have its own subtype, `PartTimeStudent_t`. A type declaration must have the flag `NOT FINAL` so that it can have subtypes. The default is `FINAL`, which means that the type can have no subtypes.

All types discussed so far in this chapter are `FINAL`. All types in applications developed before Oracle Database release 8.1.7 are `FINAL`. A type that is `FINAL` can be altered to be `NOT FINAL`. A `NOT FINAL` type with no subtypes can be altered to be `FINAL`. `Person_t` is declared as `NOT FINAL` for our example:

```
CREATE TYPE Person_t AS OBJECT
( ssn NUMBER,
  name VARCAHR2(30),
  address VARCHAR2(100)) NOT FINAL;
```

A subtype inherits all the attributes and methods declared in its supertype. It can also declare new attributes and methods, which must have different names than those of the supertype. The keyword `UNDER` identifies the supertype, like this:

```
CREATE TYPE Student_t UNDER Person_t
( deptid NUMBER,
  major VARCHAR2(30)) NOT FINAL;
```

The newly declared attributes `deptid` and `major` belong to the subtype `Student_t`. The subtype `Employee_t` is declared as, for example:

```
CREATE TYPE Employee_t UNDER Person_t
( empid NUMBER,
  mgr VARCHAR2(30));
```

#### See Also:

- ["OTT Support for Type Inheritance"](#) on page 4-20 for the classes generated by OTT for this example.

Subtype `Student_t` can have its own subtype, such as `PartTimeStudent_t`:

```
CREATE TYPE PartTimeStudent_t UNDER Student_t ( numhours NUMBER) ;
```

## Substitutability

The benefits of polymorphism derive partially from the property substitutability. Substitutability allows a value of some subtype to be used by code originally written for the supertype, without any specific knowledge of the subtype being needed in advance. The subtype value behaves to the surrounding code just like a value of the supertype would, even if it perhaps uses different mechanisms within its specializations of methods.

Instance substitutability refers to the ability to use an object value of a subtype in a context declared in terms of a supertype. REF substitutability refers to the ability to use a REF to a subtype in a context declared in terms of a REF to a supertype.

REF type attributes are substitutable, that is, an attribute defined as REF T can hold a REF to an instance of T or any of its subtypes.

Object type attributes are substitutable, that is, an attribute defined to be of (an object) type T can hold an instance of T or any of its subtypes.

Collection element types are substitutable, that is, if we define a collection of elements of type T, then it can hold instances of type T and any of its subtypes. Here is an example of object attribute substitutability:

```
CREATE TYPE Book_t AS OBJECT
( title VARCHAR2(30),
  author Person_t /* substitutable */);
```

Thus, a `Book_t` instance can be created by specifying a title string and a `Person_t` (or any subtype of `Person_t`) object:

```
Book_t('My Oracle Experience',
  Employee_t(12345, 'Joe', 'SF', 1111, NULL))
```

## NOT INSTANTIABLE Types and Methods

A type can be declared `NOT INSTANTIABLE`, which means that there is no constructor (default or user defined) for the type. Thus, it will not be possible to construct

instances of this type. The typical usage would be to define instantiable subtypes for such a type. Here is how this property is used:

```
CREATE TYPE Address_t AS OBJECT(...) NOT INSTANTIABLE NOT FINAL;
CREATE TYPE USAddress_t UNDER Address_t(...);
CREATE TYPE IntlAddress_t UNDER Address_t(...);
```

A method of a type can be declared to be `NOT INSTANTIABLE`. Declaring a method as `NOT INSTANTIABLE` means that the type is not providing an implementation for that method. Further, a type that contains any `NOT INSTANTIABLE` methods must necessarily be declared as `NOT INSTANTIABLE`. For example:

```
CREATE TYPE T AS OBJECT
(
  x NUMBER,
  NOT INSTANTIABLE MEMBER FUNCTION func1() RETURN NUMBER
) NOT INSTANTIABLE;
```

A subtype of `NOT INSTANTIABLE` can override any of the `NOT INSTANTIABLE` methods of the supertype and provide concrete implementations. If there are any `NOT INSTANTIABLE` methods remaining, the subtype must also necessarily be declared as `NOT INSTANTIABLE`.

A `NOT INSTANTIABLE` subtype can be defined under an instantiable supertype. Declaring a `NOT INSTANTIABLE` type to be `FINAL` is not useful and is not allowed.

## OCCI Support for Type Inheritance

The following calls support type inheritance.

### **Connection::getMetaData()**

This method provides information specific to inherited types. Additional attributes have been added for the properties of inherited types. For example, you can get the supertype of a type.

### **Bind and Define Functions**

The `setRef()`, `setObject()` and `setVector()` methods of the `Statement` class are used to bind `REF`, `object`, and `collections` respectively. All these functions support `REF`, `instance`, and `collection element` substitutability. Similarly, the corresponding `getxxx()` methods to fetch the data also support substitutability.

## OTT Support for Type Inheritance

Class declarations for objects with inheritance are similar to the simple object declarations except that the class is derived from the parent type class and only the fields corresponding to attributes not already in the parent class are included. The structure for these declarations is listed in [Example 4–8](#):

### **Example 4–8 OTT Support Inheritance**

```
class <typename> : public <parenttypename>
{
  protected:
    <OCCItype1> <attributename1>;
    ...
    <OCCItypen> <attributenamen>;

  public:
    void *operator new(size_t size);
```



```

void *operator new(size_t size, const Connection* conn,
                  const string& table);
string  getSQLTypeName() const;
void  getSQLTypeName(oracle::occi::Environment *env, void **schemaName,
                    unsigned int &schemaNameLen, void **typeName,
                    unsigned int &typeNameLen) const;
<typename> (void *ctx) : <parentTypename>(ctx) { };
static void *readSQL(void *ctx);
virtual void readSQL(AnyData& stream);
static void writeSQL(void *obj, void *ctx);
virtual void writeSQL(AnyData& stream);
}

```

In this structure, all variables are the same as in the simple object case. `parentTypename` refers to the name of the parent type, that is, the class name of the type from which `typename` inherits.

## A Sample OCCI Application

This section describes a sample OCCI application that uses some of the features discussed in this chapter.

### **Example 4–9 Listing of `demo2.sql` for a Sample OCCI Application**

```

drop table ADDR_TAB
/
drop table PERSON_TAB
/
drop type STUDENT
/
drop type PERSON
/
drop type ADDRESS_TAB
/
drop type ADDRESS
/
drop type FULLNAME
/
CREATE TYPE FULLNAME AS OBJECT (first_name CHAR(20), last_name CHAR(20))
/
CREATE TYPE ADDRESS AS OBJECT (state CHAR(20), zip CHAR(20))
/
CREATE TYPE ADDRESS_TAB AS VARRAY(3) OF REF ADDRESS
/
CREATE TYPE PERSON AS OBJECT (id NUMBER, name FULLNAME, curr_addr REF ADDRESS,
prev_addr_l ADDRESS_TAB) NOT FINAL
/
CREATE TYPE STUDENT UNDER PERSON (school_name CHAR(20))
/
CREATE TABLE ADDR_TAB OF ADDRESS
/
CREATE TABLE PERSON_TAB OF PERSON
/

```

### **Example 4–10 Listing of `demo2.typ` for a Sample OCCI Application**

```

TYPE FULLNAME GENERATE CFullName as MyFullName
TYPE ADDRESS GENERATE CAddress as MyAddress
TYPE PERSON GENERATE CPerson as MyPerson
TYPE STUDENT GENERATE CStudent as MyStudent

```

**Example 4–11 Listing of OTT Command that Generates Files for a Sample OCCI Application**

OTT attempts to connect with username demours; the system prompts for the password.

```
ott userid=demours intype=demo2.typ code=cpp hfile=demo2.h
    cppfile=demo2.cpp mapfile= mappings.cpp attraccess=private
```

**Example 4–12 Listing of mappings.h for a Sample OCCI Application**

```
#ifndef MAPPINGS_ORACLE
# define MAPPINGS_ORACLE

#ifdef OCCI_ORACLE
# include <occi.h>
#endif

#ifdef DEMO2_ORACLE
# include "demo2.h"
#endif

void mappings(oracle::occi::Environment* envOCCI_);

#endif
```

**Example 4–13 Listing of mappings.cpp for a Sample OCCI Application**

```
#ifndef MAPPINGS_ORACLE
# include "mappings.h"
#endif

void mappings(oracle::occi::Environment* envOCCI_)
{
    oracle::occi::Map *mapOCCI_ = envOCCI_->getMap();
    mapOCCI_->put("HR.FULLNAME", &CFullName::readSQL, &CFullName::writeSQL);
    mapOCCI_->put("HR.ADDRESS", &CAddress::readSQL, &CAddress::writeSQL);
    mapOCCI_->put("HR.PERSON", &CPerson::readSQL, &CPerson::writeSQL);
    mapOCCI_->put("HR.STUDENT", &CStudent::readSQL, &CStudent::writeSQL);
}

#endif
```

**Example 4–14 Listing of demo2.h for a Sample OCCI Application**

```
#ifndef DEMO2_ORACLE
# define DEMO2_ORACLE

#ifdef OCCI_ORACLE
# include <occi.h>
#endif

/* Make the foll changes to the generated file */
using namespace std;
using namespace oracle::occi;

class MyFullName;
class MyAddress;
class MyPerson;
/* Changes ended here */

/* GENERATED DECLARATIONS FOR THE FULLNAME OBJECT TYPE. */
class CFullName : public oracle::occi::PObject {
```

```

private:
    OCCI_STD_NAMESPACE::string FIRST_NAME;
    OCCI_STD_NAMESPACE::string LAST_NAME;

public:
    OCCI_STD_NAMESPACE::string getFirst_name() const;
    void setFirst_name(const OCCI_STD_NAMESPACE::string &value);
    OCCI_STD_NAMESPACE::string getLast_name() const;
    void setLast_name(const OCCI_STD_NAMESPACE::string &value);
    void *operator new(size_t size);
    void *operator new(size_t size, const oracle::occi::Connection * sess,
        const OCCI_STD_NAMESPACE::string& table);
    void *operator new(size_t, void *ctxOCCI_);
    void *operator new(size_t size, const oracle::occi::Connection *sess,
        const OCCI_STD_NAMESPACE::string &tableName,
        const OCCI_STD_NAMESPACE::string &typeName,
        const OCCI_STD_NAMESPACE::string &tableSchema,
        const OCCI_STD_NAMESPACE::string &typeSchema);
    string getSQLTypeName() const;
    void getSQLTypeName(oracle::occi::Environment *env, void **schemaName,
        unsigned int &schemaNameLen, void **typeName,
        unsigned int &typeNameLen) const;
    CFullName();
    CFullName(void *ctxOCCI_) : oracle::occi::PObject (ctxOCCI_) { };
    static void *readSQL(void *ctxOCCI_);
    virtual void readSQL(oracle::occi::AnyData& streamOCCI_);
    static void writeSQL(void *objOCCI_, void *ctxOCCI_);
    virtual void writeSQL(oracle::occi::AnyData& streamOCCI_);
    ~CFullName();
};

/* GENERATED DECLARATIONS FOR THE ADDRESS OBJECT TYPE. */
class CAddress : public oracle::occi::PObject {

private:
    OCCI_STD_NAMESPACE::string STATE;
    OCCI_STD_NAMESPACE::string ZIP;

public:
    OCCI_STD_NAMESPACE::string getState() const;
    void setState(const OCCI_STD_NAMESPACE::string &value);
    OCCI_STD_NAMESPACE::string getZip() const;
    void setZip(const OCCI_STD_NAMESPACE::string &value);
    void *operator new(size_t size);
    void *operator new(size_t size, const oracle::occi::Connection * sess,
        const OCCI_STD_NAMESPACE::string& table);
    void *operator new(size_t, void *ctxOCCI_);
    void *operator new(size_t size, const oracle::occi::Connection *sess,
        const OCCI_STD_NAMESPACE::string &tableName,
        const OCCI_STD_NAMESPACE::string &typeName,
        const OCCI_STD_NAMESPACE::string &tableSchema,
        const OCCI_STD_NAMESPACE::string &typeSchema);
    string getSQLTypeName() const;
    void getSQLTypeName(oracle::occi::Environment *env, void **schemaName,
        unsigned int &schemaNameLen, void **typeName,
        unsigned int &typeNameLen) const;
    CAddress();
    CAddress(void *ctxOCCI_) : oracle::occi::PObject (ctxOCCI_) { };
    static void *readSQL(void *ctxOCCI_);
    virtual void readSQL(oracle::occi::AnyData& streamOCCI_);

```

```

        static void writeSQL(void *objOCCI_, void *ctxOCCI_);
        virtual void writeSQL(oracle::occi::AnyData& streamOCCI_);
        ~CAddress();
};

/* GENERATED DECLARATIONS FOR THE PERSON OBJECT TYPE. */
class CPerson : public oracle::occi::PObject {

private:
    oracle::occi::Number ID;
    MyFullName * NAME;
    oracle::occi::Ref< MyAddress > CURR_ADDR;
    OCCI_STD_NAMESPACE::vector< oracle::occi::Ref< MyAddress > > PREV_ADDR_L;

public:
    oracle::occi::Number getId() const;
    void setId(const oracle::occi::Number &value);
    MyFullName * getName() const;
    void setName(MyFullName * value);
    oracle::occi::Ref< MyAddress > getCurr_addr() const;
    void setCurr_addr(const oracle::occi::Ref< MyAddress > &value);
    OCCI_STD_NAMESPACE::vector<oracle::occi::Ref< MyAddress>>&
        getPrev_addr_l();
    const OCCI_STD_NAMESPACE::vector<oracle::occi::Ref<MyAddress>>&
        getPrev_addr_l() const;
    void setPrev_addr_l(const OCCI_STD_NAMESPACE::vector
        <oracle::occi::Ref< MyAddress > > &value);
    void *operator new(size_t size);
    void *operator new(size_t size, const oracle::occi::Connection * sess,
        const OCCI_STD_NAMESPACE::string& table);
    void *operator new(size_t, void *ctxOCCI_);
    void *operator new(size_t size, const oracle::occi::Connection *sess,
        const OCCI_STD_NAMESPACE::string &tableName,
        const OCCI_STD_NAMESPACE::string &typeName,
        const OCCI_STD_NAMESPACE::string &tableSchema,
        const OCCI_STD_NAMESPACE::string &typeSchema);
    string getSQLTypeName() const;
    void getSQLTypeName(oracle::occi::Environment *env, void **schemaName,
        unsigned int &schemaNameLen, void **typeName,
        unsigned int &typeNameLen) const;
    CPerson();
    CPerson(void *ctxOCCI_) : oracle::occi::PObject (ctxOCCI_) { };
    static void *readSQL(void *ctxOCCI_);
    virtual void readSQL(oracle::occi::AnyData& streamOCCI_);
    static void writeSQL(void *objOCCI_, void *ctxOCCI_);
    virtual void writeSQL(oracle::occi::AnyData& streamOCCI_);
    ~CPerson();
};

/* GENERATED DECLARATIONS FOR THE STUDENT OBJECT TYPE. */
/* changes to the generated file - declarations for the MyPerson class. */
class MyPerson : public CPerson (

public:
    MyPerson(Number id_i, MyFullName *name_i, const Ref<MyAddress>& addr_i) ;
    MyPerson(void *ctxOCCI_);
    void move(const Ref<MyAddress>& new_addr);
    void displayInfo();
    MyPerson();
};

```

```

/* changes end here */

class CStudent : public MyPerson {
private:
    OCCI_STD_NAMESPACE::string SCHOOL_NAME;

public:
    OCCI_STD_NAMESPACE::string getSchool_name() const;
    void setSchool_name(const OCCI_STD_NAMESPACE::string &value);\
    void *operator new(size_t size);
    void *operator new(size_t size, const oracle::occi::Connection * sess,\
        const OCCI_STD_NAMESPACE::string& table);
    void *operator new(size_t, void *ctxOCCI_);
    void *operator new(size_t size, const oracle::occi::Connection *sess,
        const OCCI_STD_NAMESPACE::string &tableName,
        const OCCI_STD_NAMESPACE::string &typeName,
        const OCCI_STD_NAMESPACE::string &tableSchema,
        const OCCI_STD_NAMESPACE::string &typeSchema);
    string getSQLTypeName() const;
    void getSQLTypeName(oracle::occi::Environment *env, void **schemaName,
        unsigned int &schemaNameLen, void **typeName,
        unsigned int &typeNameLen) const;
    CStudent();
    CStudent(void *ctxOCCI_) : MyPerson (ctxOCCI_) { };
    static void *readSQL(void *ctxOCCI_);
    virtual void readSQL(oracle::occi::AnyData& streamOCCI_);
    static void writeSQL(void *objOCCI_, void *ctxOCCI_);
    virtual void writeSQL(oracle::occi::AnyData& streamOCCI_);
    ~CStudent();
};

/*changes made to the generated file */
/* declarations for the MyFullName class. */
class MyFullName : public CFullName
{ public:
    MyFullName(string first_name, string last_name);
    void displayInfo();
    MyFullName(void *ctxOCCI_);
};

// declarations for the MyAddress class.
class MyAddress : public CAddress
{ public:
    MyAddress(string state_i, string zip_i);
    void displayInfo();
    MyAddress(void *ctxOCCI_);
};

class MyStudent : public CStudent
{
    public :
        MyStudent(void *ctxOCCI_) ;
};
/* changes end here */
#endif

```

**Example 4–15 Listing of demo2.cpp for a Sample OCCI Application**

```

#ifndef DEMO2_ORACLE
# include "demo2.h"

```

```
#endif

/* GENERATED METHOD IMPLEMENTATIONS FOR THE FULLNAME OBJECT TYPE. */
OCCI_STD_NAMESPACE::string CFullName::getFirst_name() const
{
    return FIRST_NAME;
}

void CFullName::setFirst_name(const OCCl_STD_NAMESPACE::string &value)
{
    FIRST_NAME = value;
}

OCCI_STD_NAMESPACE::string CFullName::getLast_name() const
{
    return LAST_NAME;
}

void CFullName::setLast_name(const OCCl_STD_NAMESPACE::string &value)
{
    LAST_NAME = value;
}

void *CFullName::operator new(size_t size)
{
    return oracle::occi::PObject::operator new(size);
}

void *CFullName::operator new(size_t size, const oracle::occi::Connection *
    sess, const OCCl_STD_NAMESPACE::string& table)
{
    return oracle::occi::PObject::operator new(size, sess, table,
        (char *) "HR.FULLNAME");
}

void *CFullName::operator new(size_t size, void *ctxOCCI_)
{
    return oracle::occi::PObject::operator new(size, ctxOCCI_);
}

void *CFullName::operator new(size_t size,
    const oracle::occi::Connection *sess,
    const OCCl_STD_NAMESPACE::string &tableName,
    const OCCl_STD_NAMESPACE::string &typeName,
    const OCCl_STD_NAMESPACE::string &tableSchema,
    const OCCl_STD_NAMESPACE::string &typeSchema)
{
    return oracle::occi::PObject::operator new(size, sess, tableName,
        typeName, tableSchema, typeSchema);
}

OCCI_STD_NAMESPACE::string CFullName::getSQLTypeName() const
{
    return OCCl_STD_NAMESPACE::string("HR.FULLNAME");
}

void CFullName::getSQLTypeName(oracle::occi::Environment *env,
    void **schemaName, unsigned int &schemaNameLen, void **typeName,
    unsigned int &typeNameLen) const
{

```

```

    PObject::getSQLTypeName(env, &CFullName::readSQL, schemaName,
        schemaNameLen, typeName, typeNameLen);
}

CFullName::CFullName()
{
}

void *CFullName::readSQL(void *ctxOCCI_)
{
    MyFullName *objOCCI_ = new(ctxOCCI_) MyFullName(ctxOCCI_);
    oracle::occi::AnyData streamOCCI_(ctxOCCI_);

    try
    {
        if (streamOCCI_.isNull())
            objOCCI_->setNull();
        else
            objOCCI_->readSQL(streamOCCI_);
    }
    catch (oracle::occi::SQLException& excep)
    {
        delete objOCCI_;
        excep.setErrorCtx(ctxOCCI_);
        return (void *)NULL;
    }
    return (void *)objOCCI_;
}

void CFullName::readSQL(oracle::occi::AnyData& streamOCCI_)
{
    FIRST_NAME = streamOCCI_.getString();
    LAST_NAME = streamOCCI_.getString();
}

void CFullName::writeSQL(void *objectOCCI_, void *ctxOCCI_)
{
    CFullName *objOCCI_ = (CFullName *) objectOCCI_;
    oracle::occi::AnyData streamOCCI_(ctxOCCI_);

    try
    {
        if (objOCCI_->isNull())
            streamOCCI_.setNull();
        else
            objOCCI_->writeSQL(streamOCCI_);
    }
    catch (oracle::occi::SQLException& excep)
    {
        excep.setErrorCtx(ctxOCCI_);
    }
    return;
}

void CFullName::writeSQL(oracle::occi::AnyData& streamOCCI_)
{
    streamOCCI_.setString(FIRST_NAME);
    streamOCCI_.setString(LAST_NAME);
}

```

```
CFullName::~CFullName()
{
    int i;
}

/* GENERATED METHOD IMPLEMENTATIONS FOR THE ADDRESS OBJECT TYPE. */
OCCI_STD_NAMESPACE::string CAddress::getState() const
{
    return STATE;
}

void CAddress::setState(const OCCI_STD_NAMESPACE::string &value)
{
    STATE = value;
}

OCCI_STD_NAMESPACE::string CAddress::getZip() const
{
    return ZIP;
}

void CAddress::setZip(const OCCI_STD_NAMESPACE::string &value)
{
    ZIP = value;
}

void *CAddress::operator new(size_t size)
{
    return oracle::occi::PObject::operator new(size);
}

void *CAddress::operator new(size_t size,
                             const oracle::occi::Connection * sess,
                             const OCCI_STD_NAMESPACE::string& table)
{
    return oracle::occi::PObject::operator new(size, sess, table,
        (char *) "HR.ADDRESS");
}

void *CAddress::operator new(size_t size, void *ctxOCCI_)
{
    return oracle::occi::PObject::operator new(size, ctxOCCI_);
}

void *CAddress::operator new(size_t size,
                             const oracle::occi::Connection *sess,
                             const OCCI_STD_NAMESPACE::string &tableName,
                             const OCCI_STD_NAMESPACE::string &typeName,
                             const OCCI_STD_NAMESPACE::string &tableSchema,
                             const OCCI_STD_NAMESPACE::string &typeSchema)
{
    return oracle::occi::PObject::operator new(size, sess, tableName,
        typeName, tableSchema, typeSchema);
}

OCCI_STD_NAMESPACE::string CAddress::getSQLTypeName() const
{
    return OCCI_STD_NAMESPACE::string("HR.ADDRESS");
}
```



```

void CAddress::getSQLTypeName(oracle::occi::Environment *env,
                             void **schemaName,
                             unsigned int &schemaNameLen,
                             void **typeName,
                             unsigned int &typeNameLen) const
{
    PObject::getSQLTypeName(env, &CAddress::readSQL, schemaName,
                           schemaNameLen, typeName, typeNameLen);
}

CAddress::CAddress()
{
}

void *CAddress::readSQL(void *ctxOCCI_)
{
    MyAddress *objOCCI_ = new(ctxOCCI_) MyAddress(ctxOCCI_);
    oracle::occi::AnyData streamOCCI_(ctxOCCI_);

    try
    {
        if (streamOCCI_.isNull())
            objOCCI_->setNull();
        else
            objOCCI_->readSQL(streamOCCI_);
    }
    catch (oracle::occi::SQLException& excep)
    {
        delete objOCCI_;
        excep.setErrorCtx(ctxOCCI_);
        return (void *)NULL;
    }
    return (void *)objOCCI_;
}

void CAddress::readSQL(oracle::occi::AnyData& streamOCCI_)
{
    STATE = streamOCCI_.getString();
    ZIP = streamOCCI_.getString();
}

void CAddress::writeSQL(void *objectOCCI_, void *ctxOCCI_)
{
    CAddress *objOCCI_ = (CAddress *) objectOCCI_;
    oracle::occi::AnyData streamOCCI_(ctxOCCI_);

    try
    {
        if (objOCCI_->isNull())
            streamOCCI_.setNull();
        else
            objOCCI_->writeSQL(streamOCCI_);
    }
    catch (oracle::occi::SQLException& excep)
    {
        excep.setErrorCtx(ctxOCCI_);
    }
    return;
}

```

```
void CAddress::writeSQL(oracle::occi::AnyData& streamOCCI_)
{
    streamOCCI_.setString(STATE);
    streamOCCI_.setString(ZIP);
}

CAddress::~CAddress()
{
    int i;
}

/* GENERATED METHOD IMPLEMENTATIONS FOR THE PERSON OBJECT TYPE. */
oracle::occi::Number CPerson::getId() const
{
    return ID;
}

void CPerson::setId(const oracle::occi::Number &value)
{
    ID = value;
}

MyFullName * CPerson::getName() const
{
    return NAME;
}

void CPerson::setName(MyFullName * value)
{
    NAME = value;
}

oracle::occi::Ref< MyAddress > CPerson::getCurr_addr() const
{
    return CURR_ADDR;
}

void CPerson::setCurr_addr(const oracle::occi::Ref< MyAddress > &value)
{
    CURR_ADDR = value;
}

OCCI_STD_NAMESPACE::vector< oracle::occi::Ref< MyAddress > >&
CPerson::getPrev_addr_l()
{
    return PREV_ADDR_L;
}

const OCCI_STD_NAMESPACE::vector< oracle::occi::Ref< MyAddress > >&
CPerson::getPrev_addr_l() const
{
    return PREV_ADDR_L;
}

void CPerson::setPrev_addr_l(const OCCI_STD_NAMESPACE::vector<
oracle::occi::Ref< MyAddress > > &value)
{
    PREV_ADDR_L = value;
}

void *CPerson::operator new(size_t size)
```

```

{
    return oracle::occi::PObject::operator new(size);
}

void *CPerson::operator new(size_t size,
                            const oracle::occi::Connection * sess,
                            const OCCI_STD_NAMESPACE::string& table)
{
    return oracle::occi::PObject::operator new(size, sess, table,
        (char *) "HR.PERSON");
}

void *CPerson::operator new(size_t size, void *ctxOCCI_)
{
    return oracle::occi::PObject::operator new(size, ctxOCCI_);
}

void *CPerson::operator new(size_t size,
                            const oracle::occi::Connection *sess,
                            const OCCI_STD_NAMESPACE::string &tableName,
                            const OCCI_STD_NAMESPACE::string &typeName,
                            const OCCI_STD_NAMESPACE::string &tableSchema,
                            const OCCI_STD_NAMESPACE::string &typeSchema)
{
    return oracle::occi::PObject::operator new(size, sess, tableName,
        typeName, tableSchema, typeSchema);
}

OCCI_STD_NAMESPACE::string CPerson::getSQLTypeName() const
{
    return OCCI_STD_NAMESPACE::string("HR.PERSON");
}

void CPerson::getSQLTypeName(oracle::occi::Environment *env,
                             void **schemaName,
                             unsigned int &schemaNameLen,
                             void **typeName,
                             unsigned int &typeNameLen) const
{
    PObject::getSQLTypeName(env, &CPerson::readSQL, schemaName,
        schemaNameLen, typeName, typeNameLen);
}

CPerson::CPerson()
{
    NAME = (MyFullName *) 0;
}

void *CPerson::readSQL(void *ctxOCCI_)
{
    MyPerson *objOCCI_ = new(ctxOCCI_) MyPerson(ctxOCCI_);
    oracle::occi::AnyData streamOCCI_(ctxOCCI_);
    try
    {
        {
            if (streamOCCI_.isNull())
                objOCCI_->setNull();
            else
                objOCCI_->readSQL(streamOCCI_);
        }
    }
    catch (oracle::occi::SQLException& excep)

```

```
    {
        delete objOCCI_;
        excep.setErrorCtx(ctxOCCI_);
        return (void *)NULL;
    }
    return (void *)objOCCI_;
}

void CPerson::readSQL(oracle::occi::AnyData& streamOCCI_)
{
    ID = streamOCCI_.getNumber();
    NAME = (MyFullName *) streamOCCI_.getObject(&MyFullName::readSQL);
    CURR_ADDR = streamOCCI_.getRef();
    oracle::occi::getVectorOfRefs(streamOCCI_, PREV_ADDR_L);
}

void CPerson::writeSQL(void *objectOCCI_, void *ctxOCCI_)
{
    CPerson *objOCCI_ = (CPerson *) objectOCCI_;
    oracle::occi::AnyData streamOCCI_(ctxOCCI_);
    try
    {
        if (objOCCI_->isNull())
            streamOCCI_.setNull();
        else
            objOCCI_->writeSQL(streamOCCI_);
    }
    catch (oracle::occi::SQLException& excep)
    {
        excep.setErrorCtx(ctxOCCI_);
    }
    return;
}

void CPerson::writeSQL(oracle::occi::AnyData& streamOCCI_)
{
    streamOCCI_.setNumber(ID);
    streamOCCI_.setObject(NAME);
    streamOCCI_.setRef(CURR_ADDR);
    oracle::occi::setVectorOfRefs(streamOCCI_, PREV_ADDR_L);
}

CPerson::~CPerson()
{
    int i;
    delete NAME;
}

/* GENERATED METHOD IMPLEMENTATIONS FOR THE STUDENT OBJECT TYPE. */
OCCI_STD_NAMESPACE::string CStudent::getSchool_name() const
{
    return SCHOOL_NAME;
}

void CStudent::setSchool_name(const OCCI_STD_NAMESPACE::string &value)
{
    SCHOOL_NAME = value;
}

void *CStudent::operator new(size_t size)
```

```

{
    return oracle::occi::PObject::operator new(size);
}

void *CStudent::operator new(size_t size,
                             const oracle::occi::Connection * sess,
                             const OCCI_STD_NAMESPACE::string& table)
{
    return oracle::occi::PObject::operator new(size, sess, table,
        (char *) "HR.STUDENT");
}

void *CStudent::operator new(size_t size, void *ctxOCCI_)
{
    return oracle::occi::PObject::operator new(size, ctxOCCI_);
}

void *CStudent::operator new(size_t size,
                             const oracle::occi::Connection *sess,
                             const OCCI_STD_NAMESPACE::string &tableName,
                             const OCCI_STD_NAMESPACE::string &typeName,
                             const OCCI_STD_NAMESPACE::string &tableSchema,
                             const OCCI_STD_NAMESPACE::string &typeSchema)
{
    return oracle::occi::PObject::operator new(size, sess, tableName,
        typeName, tableSchema, typeSchema);
}

OCCI_STD_NAMESPACE::string CStudent::getSQLTypeName() const
{
    return OCCI_STD_NAMESPACE::string("HR.STUDENT");
}

void CStudent::getSQLTypeName(oracle::occi::Environment *env,
                              void **schemaName,
                              unsigned int &schemaNameLen,
                              void **typeName,
                              unsigned int &typeNameLen) const
{
    PObject::getSQLTypeName(env, &CStudent::readSQL, schemaName,
        schemaNameLen, typeName, typeNameLen);
}

CStudent::CStudent()
{
}

void *CStudent::readSQL(void *ctxOCCI_)
{
    MyStudent *objOCCI_ = new(ctxOCCI_) MyStudent(ctxOCCI_);
    oracle::occi::AnyData streamOCCI_(ctxOCCI_);

    try
    {
        if (streamOCCI_.isNull())
            objOCCI_->setNull();
        else
            objOCCI_->readSQL(streamOCCI_);
    }
    catch (oracle::occi::SQLException& excep)
    {

```

```
        delete objOCCI_;
        excep.setErrorCtx(ctxOCCI_);
        return (void *)NULL;
    }
    return (void *)objOCCI_;
}

void CStudent::readSQL(oracle::occi::AnyData& streamOCCI_)
{
    CPerson::readSQL(streamOCCI_);
    SCHOOL_NAME = streamOCCI_.getString();
}

void CStudent::writeSQL(void *objectOCCI_, void *ctxOCCI_)
{
    CStudent *objOCCI_ = (CStudent *) objectOCCI_;
    oracle::occi::AnyData streamOCCI_(ctxOCCI_);
    try
    {
        if (objOCCI_->isNull())
            streamOCCI_.setNull();
        else
            objOCCI_->writeSQL(streamOCCI_);
    }
    catch (oracle::occi::SQLException& excep)
    {
        excep.setErrorCtx(ctxOCCI_);
    }
    return;
}

void CStudent::writeSQL(oracle::occi::AnyData& streamOCCI_)
{
    CPerson::writeSQL(streamOCCI_);
    streamOCCI_.setString(SCHOOL_NAME);
}

CStudent::~CStudent()
{
    int i;
}
```

Let us assume OTT generates FULL\_NAME, ADDRSESS, PERSON, and PFGRFDENT class declarations in demo2.h. The following sample OCCI application will extend the classes generated by OTT, as specified in demo2.typ file in [Example 4-10](#), and will add some user defined methods. Note that these class declaration have been incorporated into demo2.h to ensure correct compilation.

**Example 4-16 Listing of myDemo.h for a Sample OCCI Application**

```
#ifndef MYDEMO_ORACLE
#define MYDEMO_ORACLE

#include <string>

#ifndef DEMO2_ORACLE
#include <demo2.h>
#endif

using namespace std;
```

```

using namespace oracle::occi;

// declarations for the MyFullName class.
class MyFullName : public CFullName
{ public:
    MyFullName(string first_name, string last_name);
    void displayInfo();
};

// declarations for the MyAddress class.
class MyAddress : public CAddress
{ public:
    MyAddress(string state_i, string zip_i);
    void displayInfo();
};

// declarations for the MyPerson class.
class MyPerson : public CPerson
{ public:
    MyPerson(Number id_i, MyFullname *name_i,
              const Ref<MyAddress>& addr_i);
    void move(const Ref<MyAddress>& new_addr);
    void displayInfo();
};

#endif

```

**Example 4–17 Listing for myDemo.cpp for a Sample OCCl Application**

```

#ifndef DEMO2_ORACLE
#include <demo2.h>
#endif

/* initialize MyFullName */
MyFullName::MyFullName(string first_name, string last_name)
{
    setFirst_name(first_name);
    setLast_name(last_name);
}

/* display all the information in MyFullName */
void MyFullName::displayInfo()
{
    cout << "FIRST NAME is" << getFirst_name() << endl;
    cout << "LAST NAME is" << getLast_name() << endl;
}

MyFullName::MyFullName(void *ctxOCCI_) : CFullName(ctxOCCI_)
{
}

/* METHOD IMPLEMENTATIONS FOR MyAddress CLASS. */

/* initialize MyAddress */
MyAddress::MyAddress(string state_i, string zip_i)
{
    setState(state_i);
    setZip(zip_i);
}

```

```
/* display all the information in MyAddress */
void MyAddress::displayInfo()
{
    cout << "STATE is" << getState() << endl;
    cout << "ZIP is" << getZip() << endl;
}

MyAddress::MyAddress(void *ctxOCCI_) :CAddress(ctxOCCI_)
{
}

/* METHOD IMPLEMENTATIONS FOR MyPerson CLASS. */

/* initialize MyPerson */
MyPerson::MyPerson(Number id_i, MyFullName* name_i,
                    const Ref<MyAddress>& addr_i)
{
    setId(id_i);
    setName(name_i);
    setCurr_addr(addr_i);
}

MyPerson::MyPerson(void *ctxOCCI_) :CPerson(ctxOCCI_)
{
}

/* move Person from curr_addr to new_addr */
void MyPerson::move(const Ref<MyAddress>& new_addr)
{
    // append curr_addr to the vector //
    getPrev_addr_l().push_back(getCurr_addr());
    setCurr_addr(new_addr);

    // mark the object as dirty
    this->markModified();

/* display all the information of MyPerson */
void MyPerson::displayInfo()
{
    cout << "ID is" << (int)getId() << endl;
    getName()->displayInfo();

    // de-referencing the Ref attribute using -> operator
    getCurr_addr()->displayInfo();
    cout << "Prev Addr List: " << endl;
    for (int i = 0; i < getPrev_addr_l().size(); i++)
    {
        // access the collection elements using [] operator
        (getPrev_addr_l())[i]->displayInfo();
    }
}

MyPerson::MyPerson()
{
}

MyStudent::MyStudent(void *ctxOCCI_) : CStudent(ctxOCCI_)
{
}
```



**Example 4-18 Listing of main.cpp for a Sample OCCI Application**

```

#ifndef DEMO2_ORACLE
#include <demo2.h>
#endif

#ifndef MAPPINGS_ORACLE
#include <mappings.h>
#endif

#include <iostream>
using namespace std;

int main()
{
    Environment *env = Environment::createEnvironment(Environment::OBJECT);
    mappings(env);

    try {
        Connection *conn = env->createConnection("HR", "password");

        /* Call the OTT generated function to register the mappings */
        /* create a persistent object of type ADDRESS in the database table,
           ADDR_TAB */
        MyAddress *addr1 = new(conn, "ADDR_TAB") MyAddress("CA", "94065");
        conn->commit();

        Statement *st = conn->createStatement("select ref(a) from addr_tab a");
        ResultSet *rs = st->executeQuery();
        Ref<MyAddress> r1;
        if ( rs->next() )
            r1 = rs->getRef(1);
        st->closeResultSet(rs);
        conn->terminateStatement(st);

        MyFullName * name1 = new MyFullName("Joe", "Black");

        /* create a persistent object of type Person in the database table
           PERSON_TAB */
        MyPerson *person1 = new(conn, "PERSON_TAB") MyPerson(1,name1,r1);
        conn->commit();

        /* selecting the inserted information */
        Statement *stmt = conn->createStatement();
        ResultSet *resultSet =
            stmt->executeQuery("SELECT REF(a) from person_tab a where id = 1");

        if (resultSet->next())
        {
            Ref<MyPerson> joe_ref = (Ref<MyPerson>) resultSet->getRef(1);
            joe_ref->displayInfo();

            /* create a persistent object of type ADDRESS in the database table
               ADDR_TAB */
            MyAddress *new_addr1 = new(conn, "ADDR_TAB") MyAddress("PA", "92140");
            joe_ref->move(new_addr1->getRef());
            joe_ref->displayInfo();
        }

        /* commit the transaction which results in the newly created object
           new_addr and the dirty object joe to be flushed to the server.

```

```
        Note that joe was marked dirty in move(). */
    conn->commit();

    conn->terminateStatement(stmt);
    env->terminateConnection(conn);
}

catch ( exception &x)

{
    cout << x.what () << endl;
}

    Environment::terminateEnvironment(env);
    return 0;
}
```

---

---

## Data Types

This chapter is a reference for Oracle data types used by Oracle C++ Interface applications. This information will help you understand the conversions between internal and external representations of data that occur when you transfer data between your application and the database server.

This chapter contains these topics:

- [Overview of Oracle Data Types](#)
- [Internal Data Types](#)
- [External Data Types](#)
- [Data Conversions](#)

### Overview of Oracle Data Types

Accurate communication between your C++ program and the Oracle database server is critical. OCCI applications can retrieve data from database tables by using SQL queries or they can modify existing data through the use of SQL `INSERT`, `UPDATE`, and `DELETE` functions. To facilitate communication between the host language C++ and the database server, you must be aware of how C++ data types are converted to Oracle data types and back again.

In the Oracle database, values are stored in columns in tables. Internally, Oracle represents data in particular formats called internal data types. `NUMBER`, `VARCHAR2`, and `DATE` are examples of Oracle internal data types.

OCCI applications work with host language data types, or external data types, predefined by the host language. When data is transferred between an OCCI application and the database server, the data from the database is converted from internal data types to external data types.

### OCCI Type and Data Conversion

OCCI defines an enumerator called `Type` that lists the possible data representation formats available in an OCCI application. These representation formats are called external data types. When data is sent to the database server from the OCCI application, the external data type indicates to the database server what format to expect the data. When data is requested from the database server by the OCCI application, the external data type indicates the format of the data to be returned.

For example, on retrieving a value from a `NUMBER` column, the program may be set to retrieve it in `OCCIINT` format (a signed integer format into an integer variable). Or, the

client might be set to send data in OCCIFLOAT format (floating-point format) stored in a C++ float variable to be inserted in a column of NUMBER type.

An OCI application binds input parameters to a `Statement`, by calling a `setxxx()` method (the external data type is implicitly specified by the method name), or by calling the `registerOutParam()`, `setDataBuffer()`, or `setDataBufferArray()` method (the external data type is explicitly specified in the method call). Similarly, when data values are fetched through a `ResultSet` object, the external representation of the retrieved data must be specified. This is done by calling a `getxxx()` method (the external data type is implicitly specified by the method name) or by calling the `setDataBuffer()` method (the external data type is explicitly specified in the method call).

---

**Note:** There are more external data types than internal data types. In some cases, a single external data type maps to a single internal data type; in other cases, many external data types map to a single internal data type. The many-to-one mapping provides you with added flexibility.

---

**See Also:** [External Data Types](#) on page 5-4

## Internal Data Types

The internal (built-in) data types provided by Oracle are listed in this section. A brief summary of internal Oracle data types, including description, code, and maximum size, appears in [Table 5-1](#).

**Table 5-1 Summary of Oracle Internal Data Types**

Internal Data Type	Maximum Size
BFILE	4 gigabytes
BINARY_DOUBLE	8 bytes
BINARY_FLOAT	4 bytes
CHAR	2,000 bytes
DATE	7 bytes
INTERVAL DAY TO SECOND REF	11 bytes
INTERVAL YEAR TO MONTH REF	5 bytes
LONG	2 gigabytes (2 <sup>31</sup> -1 bytes)
LONG RAW	2 gigabytes (2 <sup>31</sup> -1 bytes)
NCHAR	2,000 bytes
NUMBER	21 bytes
NVARCHAR2	4,000 bytes
RAW	2,000 bytes
REF	
BLOB	4 gigabytes
CLOB	4 gigabytes
NCLOB	4 gigabytes

**Table 5–1 (Cont.) Summary of Oracle Internal Data Types**

Internal Data Type	Maximum Size
ROWID	10 bytes
TIMESTAMP	11 bytes
TIMESTAMP WITH LOCAL TIME ZONE	7 bytes
TIMESTAMP WITH TIME ZONE	13 bytes
UROWID	4000 bytes
User-defined type (object type, VARRAY, nested table)	
VARCHAR2	4,000 bytes

**See Also:**

- *Oracle Database SQL Language Reference*
- *Oracle Database Concepts*

## Character Strings and Byte Arrays

You can use five Oracle internal data types to specify columns that contain either characters or arrays of bytes: CHAR, VARCHAR2, RAW, LONG, and LONG RAW.

CHAR, VARCHAR2, and LONG columns normally hold character data. RAW and LONG RAW hold bytes that are not interpreted as characters, for example, pixel values in a bitmapped graphics image. Character data can be transformed when passed through a gateway between networks. For example, character data passed between machines by using different languages (where single characters may be represented by differing numbers of bytes) can be significantly changed in length. Raw data is never converted in this way.

The database designer is responsible for choosing the appropriate Oracle internal data type for each column in a table. You must be aware of the many possible ways that character and byte-array data can be represented and converted between variables in the OCCI program and Oracle database tables.

## Universal Rowid (UROWID)

The universal rowid (UROWID) is a data type that can store both the logical and the physical rowid of rows in Oracle tables and in foreign tables, such as DB2 tables accessed through a gateway. Logical rowid values are primary key-based logical identifiers for the rows of index organized tables.

To use columns of the UROWID data type, the value of the COMPATIBLE initialization parameter must be set to 8.1 or higher.

The following OCCI\_SQLT types can be bound to universal rowids:

- OCCI\_SQLT\_CHR (VARCHAR2)
- OCCI\_SQLT\_VCS (VARCHAR)
- OCCI\_SQLT\_STR (NULL terminated string)
- OCCI\_SQLT\_LVC (long VARCHAR)
- OCCI\_SQLT\_AFC (CHAR)
- OCCI\_SQLT\_AVC (CHARZ)

- OCCI\_SQLT\_VST (string)
- OCCI\_SQLT\_RDD (ROWID descriptor)

## External Data Types

Communication between the host OCCI application and the Oracle database server is through the use of external data types. Specifically, external data types are mapped to C++ data types.

Table 5–2 lists the Oracle external data types, the C++ equivalent (what the Oracle internal data type is usually converted to), and the corresponding OCCI type. Note the following conditions:

- In C++ data type column, *n* stands for variable length and depends on program requirements or operating system.
- The usage of types in `Statement` class methods is as follows:
  - `setDataBuffer()` and `setDataBufferArray()`: Only types of the form `OCCI_SQLT_XXX` (for example, `OCCI_SQLT_INT`) in the `occiCommon.h` file are permitted. All types used with these methods are marked with an asterisk, `*`.
  - `registerOutParam()`: Only types of the form `OCCIxxx` (for example, `OCCIDOUBLE`, `OCCICURSOR`, and so on) on the `occiCommon.h` file are permitted. However, there are some exceptions: `OCCIANYDATA`, `OCCIMETADATA`, `OCCISTREAM`, and `OCCIBOOL` are not permitted. All types used with this method are marked with a double asterisk, `**`.
- In the `ResultSet` class, only types of the form `OCCI_SQLT_XXX` (for example, `OCCI_SQLT_INT`) in the `occiCommon.h` file are permitted for use in `setDataBuffer()` and `setDataBufferArray()` methods. These types are marked with an asterisk, `*`.
- The `TIMESTAMP` and `TIMESTAMP WITH TIME ZONE` data types are collectively known as **datetimes**. The `INTERVAL YEAR TO MONTH` and `INTERVAL DAY TO SECOND` are collectively known as **intervals**.

**Table 5–2 External Data Types and Corresponding C++ and OCCI Types**

External Data Type	C++ Type	OCCI Type
16 bit signed INTEGER *	signed short, signed int	OCCIINT
32 bit signed INTEGER *	signed int, signed long	OCCIINT
8 bit signed INTEGER *	signed char	OCCIINT
BFILE **	Bfile	OCCIBFILE
Binary FILE *	OCILobLocator	OCCI_SQLT_FILE
Binary LOB *	OCILobLocator	OCCI_SQLT_BLOB
BLOB **	Blob	OCCIBLOB
BOOL **	bool	OCCIBOOL
BYTES **	Bytes	OCCIBYTES
CHAR *	char[n]	OCCI_SQLT_AFC
CHAR **	string	OCCICHAR
Character LOB *	OCILobLocator	OCCI_SQLT_CLOB

**Table 5–2 (Cont.) External Data Types and Corresponding C++ and OCCI Types**

<b>External Data Type</b>	<b>C++ Type</b>	<b>OCCI Type</b>
CHARZ *	char[n+1]	OCCI_SQLT_RDD
CLOB **	Clob	OCCICLOB
CURSOR **	ResultSet	OCCICURSOR
DATE *	char[7]	OCCI_SQLT_DAT
DATE **	Date	OCCIDATE
DOUBLE **	double	OCCIDOUBLE
FLOAT *	float, double	OCCIFLOAT
FLOAT **	float	OCCIFLOAT
INT **	int	OCCIINT
INTERVAL DAY TO SECOND *	char[11]	OCCI_SQLT_INTERVAL_DS
INTERVAL YEAR TO MONTH *	char[5]	OCCI_SQLT_INTERVAL_YM
INTERVALDS **	IntervalDS	OCCIINTERVALDS
INTERVALYM **	IntervalYM	OCCIINTERVALYM
LONG *	char[n]	OCCI_SQLT_LNG
LONG RAW *	unsigned char[n]	OCCI_SQLT_LBI
LONG VARCHAR *	char[n+sizeof(integer)]	OCCI_SQLT_LVC
LONG VARRAW *	unsigned char[n+sizeof(integer)]	OCCI_SQLT_LVB
METADATA **	MetaData	OCCIMETADATA
NAMED DATA TYPE *	struct	OCCI_SQLT_NTY
NATIVE DOUBLE *	double	OCCIBDOUBLE
NATIVE DOUBLE **	Bdouble, double	OCCIBDOUBLE
NATIVE FLOAT *	float	OCCIBFLOAT
NATIVE FLOAT **	Bfloat, float	OCCIBFLOAT
null terminated STRING *	char[n+1]	OCCI_SQLT_STR
NUMBER *	unsigned char[21]	OCCI_SQLT_NUM
NUMBER **	Number	OCCINUMBER
POBJECT **	User defined types generated by OTT utility.	OCCIPOBJECT
RAW *	unsigned char[n]	OCCI_SQLT_BIN
REF *	OCIRef	OCCI_SQLT_REF
REF **	Ref	OCCIREF
REFANY **	RefAny	OCCIREFANY
ROWID *	OCIRowid	OCCI_SQLT_RID
ROWID **	Bytes	OCCIROWID
ROWID descriptor *	OCIRowid	OCCI_SQLT_RDD
STRING **	STL string	OCCISTRING

**Table 5–2 (Cont.) External Data Types and Corresponding C++ and OCCI Types**

External Data Type	C++ Type	OCCI Type
TIMESTAMP *	char[11]	OCCI_SQLT_TIMESTAMP
TIMESTAMP **	Timestamp	OCCITIMESTAMP
TIMESTAMP WITH LOCAL TIME ZONE *	char[7]	OCCI_SQLT_TIMESTAMP_LTZ
TIMESTAMP WITH TIME ZONE *	char[13]	OCCI_SQLT_TIMESTAMP_TZ
UNSIGNED INT *	unsigned int	OCCIUNSIGNED_INT
UNSIGNED INT **	unsigned int	OCCIUNSIGNED_INT
VARCHAR *	char[n+sizeof( short integer)]	OCCI_SQLT_VCS
VARCHAR2 *	char[n]	OCCI_SQLT_CHR
VARNUM *	char[22]	OCCI_SQLT_VNU
VARRAW *	unsigned char[n+sizeof( short integer)]	OCCI_SQLT_VBI
VECTOR **	STL vector	OCCIVECTOR

## Description of External Data Types

This section provides a description for each of the external data types.

### BFILE

The external data type BFILE allows read-only byte stream access to large files on the file system of the database server. A BFILE is a large binary data object stored in operating system files outside database tablespaces. These files use reference semantics. The Oracle server can access a BFILE provided the underlying server operating system supports stream-mode access to these operating system files.

### BDOUBLE

The BDouble interface in OCCI encapsulates the native double data and the NULL information of a column or object attribute of the type `binary_double`. The OCCI methods in [AnyData Class](#), [ResultSet Class](#) and [Statement Class](#), and the global methods that take these class objects as parameters, use the following definition for the BDOUBLE data type:

#### Example 5–1 Definition of the BDOUBLE Data Type

```
struct BDouble
{
    double value;
    bool isNull;

    BDouble()
    {
        isNull = false;
        value = 0.;
    }
};
```



## BFLOAT

The `BFloat` interface in OCCI encapsulates the native float data and the `NULL` information of a column or object attribute of the type `binary_float`. The OCCI methods in [AnyData Class](#), [ResultSet Class](#) and [Statement Class](#), and the global methods that take these class objects as parameters, use the following definition for the `BFLOAT` data type:

### Example 5–2 Definition of the `BFLOAT` Data Type

```
struct BFloat
{
    float value;
    bool isNull;

    BFloat()
    {
        isNull = false;
        value = 0.;
    }
};
```

## BLOB

The external data type `BLOB` stores unstructured binary large objects. A `BLOB` can be thought of as a bitstream with no character set semantics. `BLOB`s can store up to 4 gigabytes of binary data.

`BLOB` data types have full transactional support. Changes made through OCCI participate fully in the transaction. `BLOB` value manipulations can be committed or rolled back. You cannot save a `BLOB` locator in a variable in one transaction and then use it in another transaction or session.

## CHAR

The external data type `CHAR` is a string of characters, with a maximum length of 2000 characters. Character strings are compared by using blank-padded comparison semantics.

## CHARZ

The external data type `CHARZ` is similar to the `CHAR` data type, except that the string must be `NULL` terminated on input, and Oracle places a `NULL` terminator character at the end of the string on output. The `NULL` terminator serves only to delimit the string on input or output. It is not part of the data in the table.

## CLOB

The external data type `CLOB` stores fixed-width or varying-width character data. A `CLOB` can store up to 4 gigabytes of character data. `CLOB`s have full transactional support. Changes made through OCCI participate fully in the transaction. `CLOB` value manipulations can be committed or rolled back. You cannot save a `CLOB` locator in a variable in one transaction and then use it in another transaction or session.

## DATE

The external data type `DATE` can update, insert, or retrieve a date value using the Oracle internal seven byte date binary format, as listed in [Table 5–3](#):

**Table 5–3** *Format of the DATE Data Type*

	Byte 1	Byte 2	Byte 3	Byte 4	Byte 5	Byte 6	Byte 7
Example	Century	Year	Month	Day	Hour	Minute	Second
1: 01-JUN-2000, 3:17PM	120	100	6	1	16	18	1
2: 01-JAN-4712 BCE	53	88	1	1	1	1	1

**Example 1, 01-JUN-2000, 3:17PM:**

- The century and year bytes (1 and 2) are in excess-100 notation. Dates BCE (Before Common Era) are less than 100. Dates in the Common Era (CE), 0 and after, are greater than 100. For dates 0 and after, the first digit of both bytes 1 and 2 merely signifies that it is of the CE.
- For byte 1, the second and third digits of the century are calculated as the year (an integer) divided by 100. With integer division, the fractional portion is discarded. The following calculation is for the year 1992:  $1992 / 100 = 19$ .
- For byte 1, 119 represents the twentieth century, 1900 to 1999. A value of 120 would represent the twenty-first century, 2000 to 2099.
- For byte 2, the second and third digits of the year are calculated as the year modulo 100:  $1992 \% 100 = 92$ .
- For byte 2, 192 represents the ninety-second year of the current century. A value of 100 would represent the zeroth year of the current century.
- The year 2000 would yield 120 for byte 1 and 100 for byte 2.
- For bytes 3 through 7, valid dates begin at 01-JAN of the year. The month byte ranges from 1 to 12, the date byte ranges from 1 to 31, the hour byte ranges from 1 to 24, the minute byte ranges from 1 to 60, and the second byte ranges from 1 to 60.

**Example 2, 01-JAN-4712 BCE:**

- For years prior to 0 CE, centuries and years are represented by the difference between 100 and the number.
- For byte 1, 01-JAN-4712 BCE is century 53:  $100 - 47 = 53$ .
- For byte 2, 01-JAN-4712 BCE is year 88:  $100 - 12 = 88$ .

---

---

**Notes:**

- If no time is specified for a date, the time defaults to midnight and bytes 5 through 6 are set to 1: 1, 1, 1.
  - When you enter a date in binary format by using the external data type `DATE`, the database does not perform consistency or range checking. All data in this format must be validated before input.
  - There is little need for the external data type `DATE`. It is more convenient to convert `DATE` values to a character format, because most programs deal with dates in a character format, such as `DD-MON-YYYY`. Instead, you may use the `Date` data type.
  - When a `DATE` column is converted to a character string in your program, it is returned in the default format mask for your session, or as specified in the `INIT.ORA` file.
  - This data type is different from `OCCI DATE` which corresponds to a `C++ Date` data type.
- 
- 

**FLOAT**

The external data type `FLOAT` processes numbers with fractional parts. The number is represented in the host system's floating-point format. Normally, the length is 4 or 8 bytes.

The internal format of an Oracle number is decimal. Most floating-point implementations are binary. Oracle, therefore, represents numbers with greater precision than floating-point representations.

**INTEGER**

The external data type `INTEGER` is used for converting numbers. An external integer is a signed binary number. Its size is operating system-dependent. If the number being returned from Oracle is not an integer, then the fractional part is discarded, and no error is returned. If the number returned exceeds the capacity of a signed integer for the system, then Oracle returns an overflow on conversion error.

---

---

**Note:** A rounding error may occur when converting between `FLOAT` and `NUMBER`. Using a `FLOAT` as a bind variable in a query may return an error. You can work around this by converting the `FLOAT` to a string and using the `OCCI` type `OCCI_SQLT_CHR` or the `OCCI` type `OCCI_SQLT_STR` for the operation.

---

---

**INTERVAL DAY TO SECOND**

The external data type `INTERVAL DAY TO SECOND` stores the difference between two datetime values in terms of days, hours, minutes, and seconds. Specify this data type as follows:

```
INTERVAL DAY [(day_precision)]
  TO SECOND [(fractional_seconds_precision)]
```

This example uses the following placeholders:

- *day\_precision*: Number of digits in the DAY datetime field. Accepted values are 1 to 9. The default is 2.
- *fractional\_seconds\_precision*: Number of digits in the fractional part of the SECOND datetime field. Accepted values are 0 to 9. The default is 6.

To specify an INTERVAL DAY TO SECOND literal with nondefault day and second precision, you must specify the precisions in the literal. For example, you might specify an interval of 100 days, 10 hours, 20 minutes, 42 seconds, and 22 hundredths of a second as follows:

```
INTERVAL '100 10:20:42.22' DAY(3) TO SECOND(2)
```

You can also use abbreviated forms of the INTERVAL DAY TO SECOND literal. For example:

- INTERVAL '90' MINUTE maps to INTERVAL '00 00:90:00.00' DAY TO SECOND(2)
- INTERVAL '30:30' HOUR TO MINUTE maps to INTERVAL '00 30:30:00.00' DAY TO SECOND(2)
- INTERVAL '30' SECOND(2,2) maps to INTERVAL '00 00:00:30.00' DAY TO SECOND(2)

## INTERVAL YEAR TO MONTH

The external data type INTERVAL YEAR TO MONTH stores the difference between two datetime values by using the YEAR and MONTH datetime fields. Specify INTERVAL YEAR TO MONTH as follows:

```
INTERVAL YEAR [(year_precision)] TO MONTH
```

The placeholder *year\_precision* is the number of digits in the YEAR datetime field. The default value of *year\_precision* is 2. To specify an INTERVAL YEAR TO MONTH literal with a nondefault *year\_precision*, you must specify the precision in the literal. For example, the following INTERVAL YEAR TO MONTH literal indicates an interval of 123 years, 2 months:

```
INTERVAL '123-2' YEAR(3) TO MONTH
```

You can also use abbreviated forms of the INTERVAL YEAR TO MONTH literal. For example,

- INTERVAL '10' MONTH maps to INTERVAL '0-10' YEAR TO MONTH
- INTERVAL '123' YEAR(3) maps to INTERVAL '123-0' YEAR(3) TO MONTH

## LONG

The external data type LONG stores character strings longer than 4000 bytes and up to 2 gigabytes in a column of data type LONG. Columns of this type are only used for storage and retrieval of long strings. They cannot be used in methods, expressions, or WHERE clauses. LONG column values are generally converted to and from character strings.

## LONG RAW

The external data type LONG RAW is similar to the external data type RAW, except that it stores up to 2 gigabytes.

## LONG VARCHAR

The external data type `LONG VARCHAR` stores data from and into an Oracle `LONG` column. The first four bytes contain the length of the item. The maximum length of a `LONG VARCHAR` is 2 gigabytes.

## LONG VARRAW

The external data type `LONG VARRAW` store data from and into an Oracle `LONG RAW` column. The length is contained in the first four bytes. The maximum length is 2 gigabytes.

## NCLOB

The external data type `NCLOB` is a national character version of a `CLOB`. It stores fixed-width, multibyte national character set character (`NCHAR`), or varying-width character set data. An `NCLOB` can store up to 4 gigabytes of character text data.

`NCLOBs` have full transactional support. Changes made through `OCCI` participate fully in the transaction. `NCLOB` value manipulations can be committed or rolled back. You cannot save an `NCLOB` locator in a variable in one transaction and then use it in another transaction or session.

You cannot create an object with `NCLOB` attributes, but you can specify `NCLOB` parameters in methods.

## NUMBER

You should not need to use `NUMBER` as an external data type. If you do use it, Oracle returns numeric values in its internal 21-byte binary format and will expect this format on input. The following discussion is included for completeness only.

Oracle stores values of the `NUMBER` data type in a variable-length format. The first byte is the exponent and is followed by 1 to 20 mantissa bytes. The high-order bit of the exponent byte is the sign bit; it is set for positive numbers and it is cleared for negative numbers. The lower 7 bits represent the exponent, which is a base-100 digit with an offset of 65.

To calculate the decimal exponent, add 65 to the base-100 exponent and add another 128 if the number is positive. If the number is negative, you do the same, but subsequently the bits are inverted. For example,  $-5$  has a base-100 exponent = 62 ( $0x3e$ ). The decimal exponent is thus  $(\sim 0x3e) - 128 - 65 = 0xc1 - 128 - 65 = 193 - 128 - 65 = 0$ .

Each mantissa byte is a base-100 digit, in the range 1 to 100. For positive numbers, the digit has 1 added to it. So, the mantissa digit for the value 5 is 6. For negative numbers, instead of adding 1, the digit is subtracted from 101. So, the mantissa digit for the number  $-5$  is:  $101 - 5 = 96$ . Negative numbers have a byte containing 102 appended to the data bytes. However, negative numbers that have 20 mantissa bytes do not have the trailing 102 byte. Because the mantissa digits are stored in base-100, each byte can represent two decimal digits. The mantissa is normalized; leading zeroes are not stored.

Up to 20 data bytes can represent the mantissa. However, only 19 are guaranteed to be accurate. The 19 data bytes, each representing a base-100 digit, yield a maximum precision of 38 digits for an internal data type `NUMBER`.

Note that this data type is different from `OCCI NUMBER` which corresponds to a C++ `Number` data type.

## OCCI BFILE

**See Also:** [Chapter 13, "OCCI Application Programming Interface", Bfile Class](#) on page 13-20

## OCCI BLOB

**See Also:** [Chapter 13, "OCCI Application Programming Interface", Blob Class](#) on page 13-26

## OCCI BYTES

**See Also:** [Chapter 13, "OCCI Application Programming Interface", Bytes Class](#) on page 13-34

## OCCI CLOB

**See Also:** [Chapter 13, "OCCI Application Programming Interface", Clob Class](#) on page 13-37

## OCCI DATE

**See Also:** [Chapter 13, "OCCI Application Programming Interface", Date Class](#) on page 13-75

## OCCI INTERVALDS

**See Also:** [Chapter 13, "OCCI Application Programming Interface", IntervalDS Class](#) on page 13-97

## OCCI INTERVALYM

**See Also:** [Chapter 13, "OCCI Application Programming Interface", IntervalYM Class](#) on page 13-107

## OCCI NUMBER

**See Also:** [Chapter 13, "OCCI Application Programming Interface", Number Class](#) on page 13-142

## OCCI POBJECT

**See Also:** [Chapter 13, "OCCI Application Programming Interface", PObject Class](#) on page 13-161

## OCCI REF

**See Also:** [Chapter 13, "OCCI Application Programming Interface", Ref Class](#) on page 13-172

## OCCI REFANY

**See Also:** [Chapter 13, "OCCI Application Programming Interface", RefAny Class](#) on page 13-177

## OCCI STRING

The external data type `OCCI STRING` corresponds to an STL string.

## OCCI TIMESTAMP

**See Also:** [Chapter 13, "OCCI Application Programming Interface"](#), [Timestamp Class](#) on page 13-263

## OCCI VECTOR

The external data type `OCCI VECTOR` is used to represent collections, for example, a nested table or `VARRAY`. `CREATE TYPE num_type as VARRAY OF NUMBER(10)` can be represented in a C++ application as `vector<int>`, `vector<Number>`, and so on.

## RAW

The external data type `RAW` is used for binary data or byte strings that are not to be interpreted or processed by Oracle. `RAW` could be used, for example, for graphics character sequences. The maximum length of a `RAW` column is 2000 bytes.

When `RAW` data in an Oracle table is converted to a character string, the data is represented in hexadecimal code. Each byte of `RAW` data is represented as two characters that indicate the value of the byte, ranging from 00 to FF. If you input a character string by using `RAW`, then you must use hexadecimal coding.

## REF

The external data type `REF` is a reference to a named data type. To allocate a `REF` for use in an application, declare a variable as a pointer to a `REF`.

## ROWID

The external data type `ROWID` identifies a particular row in a database table. The `ROWID` is often returned from a query by issuing a statement similar to the following example:

```
SELECT ROWID, var1, var2 FROM db;
```

You can then use the returned `ROWID` in further `DELETE` statements.

If you are performing a `SELECT` for an `UPDATE` operation, then the `ROWID` is implicitly returned.

## STRING

The external data type `STRING` behaves like the external data type `VARCHAR2` (data type code 1), except that the external data type `STRING` must be NULL-terminated.

Note that this data type is different from `OCCI STRING` which corresponds to a C++ STL string data type.

## TIMESTAMP

The external data type `TIMESTAMP` is an extension of the `DATE` data type. It stores the year, month, and day of the `DATE` data type, plus hour, minute, and second values. Specify the `TIMESTAMP` data type as follows:

```
TIMESTAMP [(fractional_seconds_precision)]
```

The placeholder *fractional\_seconds\_precision* optionally specifies the number of digits in the fractional part of the `SECOND` datetime field and can be a number in the range 0 to 9. The default is 6. For example, you specify `TIMESTAMP (2)` as a literal as follows:

```
TIMESTAMP '1997-01-31 09:26:50.10'
```

Note that this data type is different from `OCCI TIMESTAMP`.

### **TIMESTAMP WITH LOCAL TIME ZONE**

The external data type `TIMESTAMP WITH TIME ZONE (TSTZ)` is a variant of `TIMESTAMP` that includes an explicit time zone displacement in its value. The time zone displacement is the difference (in hours and minutes) between local time and Coordinated Universal Time (UTC), formerly Greenwich Mean Time. Specify the `TIMESTAMP WITH TIME ZONE` data type as follows:

```
TIMESTAMP(fractional_seconds_precision) WITH TIME ZONE
```

The placeholder *fractional\_seconds\_precision* optionally specifies the number of digits in the fractional part of the `SECOND` datetime field and can be a number in the range 0 to 9. The default is 6.

Two `TIMESTAMP WITH TIME ZONE` values are considered identical if they represent the same instant in UTC, regardless of the `TIME ZONE` offsets stored in the data.

### **TIMESTAMP WITH TIME ZONE**

The external data type `TIMESTAMP WITH TIME ZONE` is a variant of `TIMESTAMP` that includes a **time zone displacement** in its value. The time zone displacement is the difference (in hours and minutes) between local time and Coordinated Universal Time (UTC), formerly Greenwich Mean Time. Specify the `TIMESTAMP WITH TIME ZONE` data type as follows:

```
TIMESTAMP [(fractional_seconds_precision)] WITH TIME ZONE
```

The placeholder *fractional\_seconds\_precision* optionally specifies the number of digits in the fractional part of the `SECOND` datetime field and can be a number in the range 0 to 9. The default is 6. For example, you might specify `TIMESTAMP (0) WITH TIME ZONE` as a literal as follows:

```
TIMESTAMP '1997-01-31 09:26:50+02.00'
```

### **UNSIGNED INT**

The external data type `UNSIGNED INT` is used for unsigned binary integers. The size in bytes is operating system dependent. The host system architecture determines the order of the bytes in a word. If the number being output from Oracle is not an integer, the fractional part is discarded, and no error is returned. If the number to be returned exceeds the capacity of an unsigned integer for the operating system, Oracle returns an overflow on conversion error.

### **VARCHAR**

The external data type `VARCHAR` store character strings of varying length. The first two bytes contain the length of the character string, and the remaining bytes contain the actual string. The specified length of the string in a bind or a define call must include the two length bytes, meaning the largest `VARCHAR` string is 65533 bytes long, not 65535. For converting longer strings, use the `LONG VARCHAR` external data type.



## VARCHAR2

The external data type VARCHAR2 is a variable-length string of characters up to 4000 bytes.

## VARNUM

The external data type VARNUM is similar to the external data type NUMBER, except that the first byte contains the length of the number representation. This length value does not include the length byte itself. Reserve 22 bytes to receive the longest possible VARNUM. You must set the length byte when you send a VARNUM value to the database.

**Table 5–4 VARNUM Examples**

Decimal Value	Length Byte	Exponent Byte	Mantissa Bytes	Terminator Byte
0	1	128	N/A	N/A
5	2	193	6	N/A
-5	3	62	96	102
2767	3	194	28, 68	N/A
-2767	4	61	74, 34	102
100000	2	195	11	N/A
1234567	5	196	2, 24, 46, 68	N/A

## VARRAW

The **external** data type VARRAW is similar to the external data type RAW, except that the first two bytes contain the length of the data. The specified length of the string in a bind or a define call must include the two length bytes. So the largest VARRAW string that can be received or sent is 65533 bytes, not 65535. For converting longer strings, use the LONG VARRAW data type.

## NATIVE DOUBLE

This **external** data type implements the IEEE 754 standard double-precision floating point data type. It is represented in the host system's native floating point format. The data type is stored in the Oracle Server in a byte comparable canonical format, and requires 8 bytes for storage, including the length byte. It is an alternative to Oracle NUMBER and has the following advantages over NUMBER:

- Fewer bytes used in storage
- Matches data types used by RDBMS Clients
- Supports a wider range of values used in scientific calculations.

## NATIVE FLOAT

This **external** data type implements the IEEE 754 single-precision floating point data type. It is represented in the host system's native floating point format. The data type is stored in the Oracle Server in a byte comparable canonical format, and requires 4 bytes for storage, including the length byte. It is an alternative to Oracle NUMBER and has the following advantages over NUMBER:

- Fewer bytes used in storage
- Matches data types used by RDBMS Clients
- Supports a wider range of values used in scientific calculations

## Data Conversions

Table 5–5 lists the supported conversions from Oracle internal data types to external data types, and from external data types to internal column representations. Note the following conditions:

- A REF stored in the database is converted to OCCI\_SQLT\_REF on output
- OCCI\_SQLT\_REF is converted to the internal representation of a REF on input
- A named data type stored in the database is converted to OCCI\_SQLT\_NTY (and represented by a C structure in the application) on output
- OCCI\_SQLT\_NTY (represented by a C structure in an application) is converted to the internal representation of the corresponding data type on input
- A LOB and a BFILE are represented by descriptors in OCCI applications, so there are no input or output conversions

**Table 5–5 Data Conversions Between External and Internal Data Types**

External Data Types	Internal Data Types									
	VARCHAR 2	NUMBER	LONG	ROWID	DATE	RAW	LONG RAW	CHAR	BFLOAT	BDOUBLE
CHAR	I/O	I/O	I/O	I/O <sup>1</sup>	I/O <sup>2</sup>	I/O <sup>3</sup>	I <sup>3,5</sup>	I/O	I/O	I/O
CHARZ	I/O	I/O	I/O	I/O <sup>1</sup>	I/O <sup>2</sup>	I/O <sup>3</sup>	I <sup>3,5</sup>	I/O	-	-
DATE	I/O	-	I	-	I/O	-	-	I/O	-	-
DECIMAL	I/O <sup>4</sup>	I/O	I	-	-	-	-	I/O <sup>4</sup>	-	-
FLOAT	I/O <sup>4</sup>	I/O	I	-	-	-	-	I/O <sup>4</sup>	I/O	I/O
INTEGER	I/O <sup>4</sup>	I/O	I	-	-	-	-	I/O <sup>4</sup>	I/O	I/O
LONG	I/O	I/O	I/O	I/O <sup>1</sup>	I/O <sup>2</sup>	I/O <sup>3</sup>	I/O <sup>3,5</sup>	I/O	I/O	I/O
LONG RAW	O <sup>6</sup>	-	I <sup>5,6</sup>	-	-	I/O	I/O	O <sup>6</sup>	-	-
LONG VARCHAR	I/O	I/O	I/O	I/O <sup>1</sup>	I/O <sup>2</sup>	I/O <sup>3</sup>	I/O <sup>3,5</sup>	I/O	I/O	I/O
LONG VARRAW	I/O <sup>6</sup>	-	I <sup>5,6</sup>	-	-	I/O	I/O	I/O <sup>6</sup>	-	-
NUMBER	I/O <sup>4</sup>	I/O	I	-	-	-	-	I/O <sup>4</sup>	I/O	I/O
OCCI BDouble	I/O	I/O	I	-	-	-	-	I/O	I/O	I/O
OCCI BFloat	I/O	I/O	I	-	-	-	-	I/O	I/O	I/O
OCCI Bytes	I/O <sup>6</sup>	-	I <sup>5,6</sup>	-	-	I/O	I/O	I/O <sup>6</sup>	-	-
OCCI Date	I/O	-	I	-	I/O	-	-	I/O	-	-
OCCI Number	I/O <sup>4</sup>	I/O	I	-	-	-	-	I/O <sup>4</sup>	I/O	I/O
OCCI Timestamp	-	-	-	-	-	-	-	-	-	-
RAW	I/O <sup>6</sup>	-	I <sup>5,6</sup>	-	-	I/O	I/O	I/O <sup>6</sup>	-	-
ROWID	I	-	I	I/O	-	-	-	I	-	-
STL string	I/O	I/O	I/O	I/O <sup>1</sup>	I/O <sup>2</sup>	I/O <sup>3</sup>	I/O <sup>3</sup>	-	I/O <sup>4</sup>	I/O <sup>4</sup>
STRING	I/O	I/O	I/O	I/O <sup>1</sup>	I/O <sup>2</sup>	I/O <sup>3</sup>	I/O <sup>3,5</sup>	I/O	I/O	I/O
UNSIGNED	I/O <sup>4</sup>	I/O	I	-	-	-	-	I/O <sup>4</sup>	I/O	I/O
VARCHAR	I/O	I/O	I/O	I/O <sup>1</sup>	I/O <sup>2</sup>	I/O <sup>3</sup>	I/O <sup>3</sup>	-	I/O	I/O

**Table 5–5 (Cont.) Data Conversions Between External and Internal Data Types**

External Data Types	Internal Data Types									
	VARCHAR2	NUMBER	LONG	ROWID	DATE	RAW	LONG RAW	CHAR	BFLOAT	BDOUBLE
VARCHAR2	I/O	I/O	I/O	I/O <sup>1</sup>	I/O <sup>2</sup>	I/O <sup>3</sup>	I/O <sup>3,5</sup>	I/O	I/O	I/O
VARNUM	I/O <sup>4</sup>	I/O	I	-	-	-	-	I/O <sup>4</sup>	I/O	I/O
VARRAW	I/O <sup>6</sup>	-	I <sup>5,6</sup>	-	-	I/O	I/O	I/O <sup>6</sup>	-	-

**Note:** Conversions valid for I (Input only), O (Output Only), I/O (Input or Output)

1. Must be in Oracle ROWID format for input; returned in Oracle ROWID format on output.
2. Must be in Oracle DATE format for input; returned in Oracle DATE format on output.
3. Must be in hexadecimal format for input; returned in hexadecimal format on output.
4. Must represent a valid number for output.
5. Length must be less than or equal to 2000 characters.
6. Stored in hexadecimal format on output; must be in hexadecimal format on output.

## Data Conversions for LOB Data Types

**Table 5–6 Data Conversions for LOBs**

EXTERNAL DATA TYPES	INTERNAL DATA TYPES	
	CLOB	BLOB
VARCHAR	I/O	-
CHAR	I/O	-
LONG	I/O	-
LONG VARCHAR	I/O	-
STL String	I/O	-
RAW	-	I/O
VARRAW	-	I/O
LONG RAW	-	I/O
LONG VARRAW	-	I/O
OCCI Bytes	-	I/O

**See Also:** *Oracle Database SecureFiles and Large Objects Developer's Guide* for an introduction to LOB data types.

## Data Conversions for Date, Timestamp, and Interval Data Types

You can also use one of the character data types for the host variable used in a fetch or insert operation from or to a datetime or interval column. Oracle will do the conversion between the character data type and datetime/interval data type for you.

**Table 5–7 Data Conversions for Date, Timestamp, and Interval Data Types**

External Types	Internal Types						
	VARCHAR, CHAR	DATE	TS	TSTZ	TSLTZ	INTERVAL YEAR TO MONTH	INTERVAL DAY TO SECOND
VARCHAR2, CHAR	I/O	I/O	I/O	I/O	I/O	I/O	I/O
STL String	I/O	I/O	I/O	I/O	I/O	I/O	I/O
DATE	I/O	I/O	I/O	I/O	I/O	-	-
OCCI Date	I/O	I/O	I/O	I/O	I/O	-	-
ANSI DATE	I/O	I/O	I/O	I/O	I/O	-	-
TIMESTAMP (TS)	I/O	I/O	I/O	I/O	I/O	-	-
OCCI Timestamp	I/O	I/O	I/O	I/O	I/O	-	-
TIMESTAMP WITH TIME ZONE (TSTZ)	I/O	I/O	I/O	I/O	I/O	-	-
TIMESTAMP WITH LOCAL TIME ZONE (TSLTZ)	I/O	I/O	I/O	I/O	I/O	-	-
INTERVAL YEAR TO MONTH	I/O	-	-	-	-	I/O	-
OCCI IntervalYM	I/O	-	-	-	-	I/O	-
INTERVAL DAY TO SECOND	I/O	-	-	-	-	-	I/O
OCCI IntervalDS	I/O	-	-	-	-	-	I/O

These consideration apply when converting between Date, Timestamp and Interval data types:

- When assigning a source with time zone to a target without a time zone, the time zone portion of the source is ignored. On assigning a source without a time zone to a target with a time zone, the time zone of the target is set to the session's default time zone.
- When assigning an Oracle DATE to a TIMESTAMP, the TIME portion of the DATE is copied over to the TIMESTAMP. When assigning a TIMESTAMP to Oracle DATE, the TIME portion of the result DATE is set to zero. This is done to encourage migration of Oracle DATE to ANSI compliant DATETIME data types.
- (When assigning an ANSI DATE to an Oracle DATE or a TIMESTAMP, the TIME portion of the Oracle DATE and the TIMESTAMP are set to zero. When assigning an Oracle DATE or a TIMESTAMP to an ANSI DATE, the TIME portion is ignored.
- When assigning a DATETIME to a character string, the DATETIME is converted using the session's default DATETIME format. When assigning a character string to a DATETIME, the string must contain a valid DATETIME value based on the session's default DATETIME format.
- When assigning a character string to an INTERVAL, the character string must be a valid INTERVAL character format.
- When converting from TSLTZ to CHAR, DATE, TIMESTAMP and TSTZ, the value will be adjusted to the session time zone.
- When converting from CHAR, DATE, and TIMESTAMP to TSLTZ, the session time zone will be stored in memory.

- When assigning TSLTZ to ANSI DATE, the time portion will be 0.
- When converting from TSTZ, the time zone which the time stamp is in will be stored in memory.
- When assigning a character string to an interval, the character string must be a valid interval character format.



This chapter describes how to retrieve metadata about result sets or the database as a whole.

This chapter contains these topics:

- [Overview of Metadata](#)
- [Describing Database Metadata](#)

## Overview of Metadata

Database objects have various attributes that describe them; you can obtain information about a particular schema object by performing a `DESCRIBE` operation. The result can be accessed as an object of the `Metadata` class by passing object attributes as arguments to the various methods of the `Metadata` class.

You can perform an explicit `DESCRIBE` operation on the database as a whole, on the types and properties of the columns contained in a `ResultSet` class, or on any of the following schema and subschema objects, such as tables, types, sequences, views, type attributes, columns, procedures, type methods, arguments, functions, collections, results, packages, synonyms, and lists

You must specify the type of the attribute you are looking for. By using the `getAttributeCount()`, `getAttributeId()`, and `getAttributeType()` methods of the `MetaData` class, you can scan through each available attribute.

All `DESCRIBE` information is cached until the last reference to it is deleted. Users are in this way prevented from accidentally trying to access `DESCRIBE` information that is already freed.

You obtain metadata by calling the `getMetaData()` method on the `Connection` class in case of an explicit describe, or by calling the `getColumnListMetaData()` method on the `ResultSet` class to get the metadata of the result set columns. Both methods return a `MetaData` object with the describing information. The `MetaData` class provides the `getxxx()` methods to access this information.

**See Also:** [Table 13–26, "Enumerated Values Used by MetaData Class"](#) on page 13-127

## Notes on Types and Attributes

When performing `DESCRIBE` operations, be aware of the following issues:

- The `ATTR_TYPECODE` returns type codes that represent the type supplied when you created a new type by using the `CREATE TYPE` statement. These type codes

are of the enumerated type `TypeCode`, which are represented by `OCCI_TYPECODE` constants.

---

**Note:** Internal PL/SQL types (boolean, indexed table) are not supported.

---

- The `ATTR_DATA_TYPE` returns types that represent the data types of the database columns. These values are of enumerated type `Type`. For example, `LONG` types return `OCCI_SQLT_LNG` types.

## Describing Database Metadata

Describing database metadata is equivalent to an explicit `DESCRIBE` operation. The object to describe must be an object in the schema. In describing a type, you call the `getMetaData()` method from the connection, passing the name of the object or a `RefAny` object. To do this, you must initialize the environment in the `OBJECT` mode. The `getMetaData()` method returns an object of type `MetaData`. Each type of `MetaData` object has a list of attributes that are part of the describe tree. The describe tree can then be traversed recursively to point to subtrees that contain more information. More information about an object can be obtained by calling the `getxxx()` methods.

If you need to construct a browser that describes the database and its objects recursively, then you can access information regarding the number of attributes for each object in the database (including the database), the attribute ID listing, and the attribute types listing. By using this information, you can recursively traverse the describe tree from the top node (the database) to the columns in the tables, the attributes of a type, the parameters of a procedure or function, and so on.

For example, consider the typical case of describing a table and its contents. You call the `getMetaData()` method from the connection, passing the name of the table to be described. The `MetaData` object returned contains the table information. Since you are aware of the type of the object that you want to describe (table, column, type, collection, function, procedure, and so on), you can obtain the attribute list. You can retrieve the value into a variable of the type specified in the table by calling the corresponding `getxxx()` method.

## Metadata Code Examples

This section provides code examples for using metadata:

- [Example 6-1, "How to Obtain Metadata About Attributes of a Simple Database Table"](#) on page 6-2
- [Example 6-2, "How to Obtain Metadata from a Column Containing User-Defined Types"](#) on page 6-3
- [Example 6-3, "How to Obtain Object Metadata from a Reference"](#) on page 6-4
- [Example 6-4, "How to Obtain Metadata About a Select List from a ResultSet Object"](#) on page 6-5

### **Example 6-1 How to Obtain Metadata About Attributes of a Simple Database Table**

This example demonstrates how to obtain metadata about attributes of a simple database table:

```
/* Create an environment and a connection to the HR database */
```



```

.
.
/* Call the getMetaData method on the Connection object obtainedv*/
MetaData emptab_metaData = connection->getMetaData(
    "EMPLOYEES", MetaData::PTYPE_TABLE);
/* Now that you have the metadata information on the EMPLOYEES table,
   call the getxxx methods using the appropriate attributes */

/* Call getString */
cout<<"Schema:"<<
    (emptab_metaData.getString(MetaData::ATTR_OBJ_SCHEMA))<<endl;

if(emptab_metaData.getInt(
    emptab_metaData::ATTR_PTYPE)==MetaData::PTYPE_TABLE)
    cout<<"EMPLOYEES is a table"<<endl;
else
    cout<<"EMPLOYEES is not a table"<<endl;

/* Call getInt to get the number of columns in the table */
int columnCount=emptab_metaData.getInt(MetaData::ATTR_NUM_COLS);
cout<<"Number of Columns:"<<columnCount<<endl;

/* Call getTimestamp to get the timestamp of the table object */
Timestamp tstamp = emptab_metaData.getTimestamp(MetaData::ATTR_TIMESTAMP);
/* Now that you have the value of the attribute as a Timestamp object,
   you can call methods to obtain the components of the timestamp */
int year;
unsigned int month, day;
tstamp.getData(year, month, day);

/* Call getVector for attributes of list type, e.g. ATTR_LIST_COLUMNS */
vector<MetaData>listOfColumns;
listOfColumns=emptab_metaData.getVector(MetaData::ATTR_LIST_COLUMNS);

/* Each of the list elements represents a column metadata,
   so now you can access the column attributes*/
for (int i=0;i<listOfColumns.size();i++)
{
    MetaData columnObj=listOfColumns[i];
    cout<<"Column Name:"<<(columnObj.getString(MetaData::ATTR_NAME))<<endl;
    cout<<"Data Type:"<<(columnObj.getInt(MetaData::ATTR_DATA_TYPE))<<endl;
    .
    .
    /* and so on to obtain metadata on other column specific attributes */
}

```

### **Example 6–2 How to Obtain Metadata from a Column Containing User-Defined Types**

This example demonstrates how to obtain metadata from a column that contains user-defined types database table.

```

/* Create an environment and a connection to the HR database */
...
/* Call the getMetaData method on the Connection object obtained */
MetaData custtab_metaData = connection->getMetaData(
    "CUSTOMERS", MetaData::PTYPE_TABLE);

/* Have metadata information on CUSTOMERS table; call the getxxx methods */
/* Call getString */
cout<<"Schema:"<<(custtab_metaData.getString(MetaData::ATTR_OBJ_SCHEMA))
    <<endl;

```

```

if(custtab_metaData.getInt(custtab_metaData::ATTR_PTYPE)==MetaData::PTYPE_TABLE)
    cout<<"CUSTOMERS is a table"<<endl;
else
    cout<<"CUSTOMERS is not a table"<<endl;

/* Call getVector to obtain list of columns in the CUSTOMERS table */
vector<MetaData>listOfColumns;
listOfColumns=custtab_metaData.getVector(MetaData::ATTR_LIST_COLUMNS);

/* Assuming metadata for column cust_address_typ is fourth element in list*/
MetaData customer_address=listOfColumns[3];

/* Obtain the metadata for the customer_address attribute */
int typcode = customer_address.getInt(MetaData::ATTR_TYPECODE);
if(typcode==OCCI_TYPECODE_OBJECT)
    cout<<"customer_address is an object type"<<endl;
else
    cout<<"customer_address is not an object type"<<endl;

string objectName=customer_address.getString(MetaData::ATTR_OBJ_NAME);

/* Now that you have the name of the address object,
the metadata of the attributes of the type can be obtained by using
getMetaData on the connection by passing the object name
*/
MetaData address = connection->getMetaData(objectName);

/* Call getVector to obtain the list of the address object attributes */
vector<MetaData> attributeList =
    address.getVector(MetaData::ATT_LIST_TYPE_ATTRS);

/* and so on to obtain metadata on other address object specific attributes */

```

### **Example 6-3 How to Obtain Object Metadata from a Reference**

This example demonstrates how to obtain metadata about an object when using a reference to it:

```

Type ADDRESS(street VARCHAR2(50), city VARCHAR2(20));
Table Person(id NUMBER, addr REF ADDRESS);

/* Create an environment and a connection to the HR database */
.
.
/* Call the getMetaData method on the Connection object obtained */
MetaData perstab_metaData = connection->getMetaData(
    "Person", MetaData::PTYPE_TABLE);

/* Now that you have the metadata information on the Person table,
call the getxxx methods using the appropriate attributes */
/* Call getString */
cout<<"Schema:"<<(perstab_metaData.getString(MetaData::ATTR_OBJ_SCHEMA))<<endl;

if(perstab_metaData.getInt(perstab_metaData::ATTR_PTYPE)==MetaData::PTYPE_TABLE)
    cout<<"Person is a table"<<endl;
else
    cout<<"Person is not a table"<<endl;

/* Call getVector to obtain the list of columns in the Person table*/
vector<MetaData>listOfColumns;
listOfColumns=perstab_metaData.getVector(MetaData::ATTR_LIST_COLUMNS);

```

```

/* Each of the list elements represents a column metadata,
   so now get the data type of the column by passing ATTR_DATA_TYPE
   to getInt */
for(int i=0;i<numCols;i++)
{
    int dataType=colList[i].getInt(MetaData::ATTR_DATA_TYPE);
    /* If the data type is a reference, get the Ref and obtain the metadata
       about the object by passing the Ref to getMetaData */
    if(dataType==SQLT_REF)
        RefAny refTdo=colList[i].getRef(MetaData::ATTR_REF_TDO);

    /* Now you can obtain the metadata about the object as shown
       MetaData tdo_metaData=connection->getMetaData(refTdo);

    /* Now that you have the metadata about the TDO, you can obtain the metadata
       about the object */
}

```

#### **Example 6-4 How to Obtain Metadata About a Select List from a ResultSet Object**

This example demonstrates how to obtain metadata about a select list from a `ResultSet`.

```

/* Create an environment and a connection to the database */
...
/* Create a statement and associate it with a select clause */
string sqlStmt="SELECT * FROM EMPLOYEES";
Statement *stmt=conn->createStatement(sqlStmt);

/* Execute the statement to obtain a ResultSet */
ResultSet *rset=stmt->executeQuery();

/* Obtain the metadata about the select list */
vector<MetaData>cmd=rset->getColumnListMetaData();

/* The metadata is a column list and each element is a column metaData */
int dataType=cmd[i].getInt(MetaData::ATTR_DATA_TYPE);
...

```

The `getMetaData` method is called for the `ATTR_COLLECTION_ELEMENT` attribute only.

## Attribute Reference

This section describes the attributes belonging to schema and subschema objects.

### Parameter Attributes

All elements have some attributes specific to that element and some generic attributes.

[Table 6-1](#) describes the attributes that belong to all elements:

**Table 6-1 Attributes that Belong to All Elements**

Attribute	Description	Attribute Data Type
ATTR_OBJ_ID	Object or schema ID	unsigned int
ATTR_OBJ_NAME	Object, schema, or database name	string

**Table 6–1 (Cont.) Attributes that Belong to All Elements**

Attribute	Description	Attribute Data Type
ATTR_OBJ_SCHEMA	Schema where object is located	string
ATTR_OBJ_PTYPE	Type of information described by the parameter. Possible values are: PTYPE_TABLE, Table PTYPE_VIEW, View PTYPE_PROC, Procedure PTYPE_FUNC, Function PTYPE_PKG, Package PTYPE_TYPE, Type PTYPE_TYPE_ATTR, Attribute of a type PTYPE_TYPE_COLL, Collection type information PTYPE_TYPE_METHOD, A method of a type PTYPE_SYN, Synonym PTYPE_SEQ, Sequence PTYPE_COL, Column of a table or view PTYPE_ARG, Argument of a function or procedure PTYPE_TYPE_ARG, Argument of a type method PTYPE_TYPE_RESULT, Results of a method PTYPE_SCHEMA, Schema PTYPE_DATABASE, Database	int
ATTR_TIMESTAMP	The <code>TIMESTAMP</code> of the object this description is based on (Oracle <code>DATE</code> format).	Timestamp

The sections that follow list attributes specific to different types of elements.

## Table and View Attributes

A parameter for a table or view (type `PTYPE_TABLE` or `PTYPE_VIEW`) has the following type-specific attributes described in [Table 6–2](#):

**Table 6–2 Attributes that Belong to Tables or Views**

Attribute	Description	Attribute Data Type
ATTR_OBJID	Object ID	unsigned int
ATTR_NUM_COLS	Number of columns	int
ATTR_LIST_COLUMNS	Column list (type <code>PTYPE_LIST</code> )	vector<MetaData>
ATTR_REF_TDO	REF to the object type that is being described	RefAny
ATTR_IS_TEMPORARY	Identifies whether the table or view is temporary	bool
ATTR_IS_TYPED	Identifies whether the table or view is typed	bool
ATTR_DURATION	Duration of a temporary table. Values can be: <ul style="list-style-type: none"> <li>▪ <code>DURATION_SESSION</code> (session)</li> <li>▪ <code>DURATION_TRANS</code> (transaction)</li> <li>▪ <code>DURATION_NULL</code> (table not temporary)</li> </ul>	int

The additional attributes belonging to tables are described in [Table 6–3](#).

**Table 6–3 Attributes Specific to Tables**

Attribute	Description	Attribute Data Type
ATTR_DBA	Data block address of the segment header	unsigned int

**Table 6–3 (Cont.) Attributes Specific to Tables**

Attribute	Description	Attribute Data Type
ATTR_TABLESPACE	Tablespace the table resides on	int
ATTR_CLUSTERED	Identifies whether the table is clustered	bool
ATTR_PARTITIONED	Identifies whether the table is partitioned	bool
ATTR_INDEX_ONLY	Identifies whether the table is index only	bool

## Procedure, Function, and Subprogram Attributes

A parameter for a procedure or function (type PTYPE\_PROC or PTYPE\_FUNC) has the type-specific attributes described in [Table 6–4](#).

**Table 6–4 Attributes that Belong to Procedures or Functions**

Attribute	Description	Attribute Data Type
ATTR_LIST_ARGUMENTS	Argument list; refer to <a href="#">List Attributes</a> on page 6-13.	vector<MetaData>
ATTR_IS_INVOKER_RIGHTS	Identifies whether the procedure or function has invoker's rights.	int

The additional attributes belonging to package subprograms are described in [Table 6–5](#).

**Table 6–5 Attributes that Belong to Package Subprograms**

Attribute	Description	Attribute Data Type
ATTR_NAME	Name of procedure or function	string
ATTR_OVERLOAD_ID	Overloading ID number (relevant in case the procedure or function is part of a package and is overloaded). Values returned may be different from direct query of a PL/SQL function or procedure.	int

## Package Attributes

A parameter for a package (type PTYPE\_PKG) has the type-specific attributes described in [Table 6–6](#).

**Table 6–6 Attributes that Belong to Packages**

Attribute	Description	Attribute Data Type
ATTR_LIST_SUBPROGRAMS	Subprogram list; refer to <a href="#">List Attributes</a> on page 6-13.	vector<MetaData>
ATTR_IS_INVOKER_RIGHTS	Identifies whether the package has invoker's rights	bool

## Type Attributes

A parameter for a type (type PTYPE\_TYPE) has attributes described in [Table 6–7](#).

**Table 6–7 Attributes that Belong to Types**

Attribute	Description	Attribute Data Type
ATTR_REF_TDO	Returns the in-memory ref of the type descriptor object for the type, if the column type is an object type.	RefAny

**Table 6–7 (Cont.) Attributes that Belong to Types**

Attribute	Description	Attribute Data Type
ATTR_TYPECODE	Type code. Can be: <ul style="list-style-type: none"> <li>■ OCCI_TYPECODE_OBJECT</li> <li>■ OCCI_TYPECODE_NAMEDCOLLECTION</li> </ul> Refer to <a href="#">Notes on Types and Attributes</a> on page 6-1.	int
ATTR_COLLECTION_TYPECODE	Type code of collection if type is collection; invalid otherwise. Can be: <ul style="list-style-type: none"> <li>■ OCCI_TYPECODE_VARRAY</li> <li>■ OCCI_TYPECODE_TABLE</li> </ul> Refer to <a href="#">Notes on Types and Attributes</a> on page 6-1.	int
ATTR_VERSION	A NULL-terminated string containing the user-assigned version	string
ATTR_IS_FINAL_TYPE	Identifies whether this is a final type	bool
ATTR_IS_INSTANTIABLE_TYPE	Identifies whether this is an instantiable type	bool
ATTR_IS_SUBTYPE	Identifies whether this is a subtype	bool
ATTR_SUPERTYPE_SCHEMA_NAME	Name of the schema containing the supertype	string
ATTR_SUPERTYPE_NAME	Name of the supertype	string
ATTR_IS_INVOKER_RIGHTS	Identifies whether this type is invoker's rights	bool
ATTR_IS_INCOMPLETE_TYPE	Identifies whether this type is incomplete	bool
ATTR_IS_SYSTEM_TYPE	Identifies whether this is a system type	bool
ATTR_IS_PREDEFINED_TYPE	Identifies whether this is a predefined type	bool
ATTR_IS_TRANSIENT_TYPE	Identifies whether this is a transient type	bool
ATTR_IS_SYSTEM_GENERATED_TYPE	Identifies whether this is a system-generated type	bool
ATTR_HAS_NESTED_TABLE	Identifies whether this type contains a nested table attribute	bool
ATTR_HAS_LOB	Identifies whether this type contains a LOB attribute	bool
ATTR_HAS_FILE	Identifies whether this type contains a FILE attribute	bool
ATTR_COLLECTION_ELEMENT	Handle to collection element Refer to <a href="#">Collection Attributes</a> on page 6-10	MetaData
ATTR_NUM_TYPE_ATTRS	Number of type attributes	unsigned int
ATTR_LIST_TYPE_ATTRS	List of type attributes Refer to <a href="#">List Attributes</a> on page 6-13	vector<MetaData>
ATTR_NUM_TYPE_METHODS	Number of type methods	unsigned int
ATTR_LIST_TYPE_METHODS	List of type methods Refer to <a href="#">List Attributes</a> on page 6-13	vector<MetaData>
ATTR_MAP_METHOD	Map method of type Refer to <a href="#">Type Method Attributes</a> on page 6-9	MetaData
ATTR_ORDER_METHOD	Order method of type; refer to <a href="#">Type Method Attributes</a> on page 6-9	MetaData

## Type Attribute Attributes

A parameter for an attribute of a type (type `P_TYPE_TYPE_ATTR`) has the attributes described in [Table 6-8](#).

**Table 6-8 Attributes that Belong to Type Attributes**

Attribute	Description	Attribute Data Type
<code>ATTR_DATA_SIZE</code>	Maximum size of the type attribute. This length is returned in bytes and not characters for strings and raws. Returns 22 for <code>NUMBER</code> .	<code>int</code>
<code>ATTR_TYPECODE</code>	Type code Refer to <a href="#">Notes on Types and Attributes</a> on page 6-1.	<code>int</code>
<code>ATTR_DATA_TYPE</code>	Data type of the type attribute Refer to <a href="#">Notes on Types and Attributes</a> on page 6-1.	<code>int</code>
<code>ATTR_NAME</code>	A pointer to a string that is the type attribute name	<code>string</code>
<code>ATTR_PRECISION</code>	Precision of numeric type attributes. If the precision is nonzero and scale is <code>-127</code> , then it is a <code>FLOAT</code> ; otherwise a <code>NUMBER(p, s)</code> . If precision is 0, then <code>NUMBER(p, s)</code> can be represented simply by <code>NUMBER</code> .	<code>int</code>
<code>ATTR_SCALE</code>	Scale of numeric type attributes. If the precision is nonzero and scale is <code>-127</code> , then it is a <code>FLOAT</code> ; otherwise a <code>NUMBER(p, s)</code> . If precision is 0, then <code>NUMBER(p, s)</code> can be represented simply as <code>NUMBER</code> .	<code>int</code>
<code>ATTR_TYPE_NAME</code>	A string that is the type name. The returned value will contain the type name if the data type is <code>SQLT_NTY</code> or <code>SQLT_REF</code> . If the data type is <code>SQLT_NTY</code> , then the name of the named data type's type is returned. If the data type is <code>SQLT_REF</code> , then the type name of the named data type pointed to by the <code>REF</code> is returned.	<code>string</code>
<code>ATTR_SCHEMA_NAME</code>	String with the schema name under which the type has been created	<code>string</code>
<code>ATTR_REF_TDO</code>	Returns the in-memory <code>REF</code> of the <code>TDO</code> for the type, if the column type is an object type.	<code>RefAny</code>
<code>ATTR_CHARSET_ID</code>	Character set ID, if the type attribute is of a string or character type	<code>int</code>
<code>ATTR_CHARSET_FORM</code>	Character set form, if the type attribute is of a string or character type	<code>int</code>
<code>ATTR_FSPRECISION</code>	The fractional seconds precision of a datetime or interval	<code>int</code>
<code>ATTR_LFPRECISION</code>	The leading field precision of an interval	<code>int</code>

## Type Method Attributes

A parameter for a method of a type (type `P_TYPE_TYPE_METHOD`) has the attributes described in [Table 6-9](#).

**Table 6-9 Attributes that Belong to Type Methods**

Attribute	Description	Attribute Data Type
<code>ATTR_NAME</code>	Name of method (procedure or function)	<code>string</code>
<code>ATTR_ENCAPSULATION</code>	Encapsulation level of the method; can be: <ul style="list-style-type: none"> <li>▪ <code>OCCI_TYPEENCAP_PRIVATE</code></li> <li>▪ <code>OCCI_TYPEENCAP_PUBLIC</code></li> </ul>	<code>int</code>
<code>ATTR_LIST_ARGUMENTS</code>	Argument list	<code>vector&lt;MetaData&gt;</code>

**Table 6–9 (Cont.) Attributes that Belong to Type Methods**

Attribute	Description	Attribute Data Type
ATTR_IS_CONSTRUCTOR	Identifies whether the method is a constructor	bool
ATTR_IS_DESTRUCTOR	Identifies whether the method is a destructor	bool
ATTR_IS_OPERATOR	Identifies whether the method is an operator	bool
ATTR_IS_SELFISH	Identifies whether the method is selfish	bool
ATTR_IS_MAP	Identifies whether the method is a map method	bool
ATTR_IS_ORDER	Identifies whether the method is an order method	bool
ATTR_IS_RNDS	Identifies whether "Read No Data State" is set for the method	bool
ATTR_IS_RNPS	Identifies whether "Read No Process State" is set for the method	bool
ATTR_IS_WNDS	Identifies whether "Write No Data State" is set for the method	bool
ATTR_IS_WNPS	Identifies whether "Write No Process State" is set for the method	bool
ATTR_IS_FINAL_METHOD	Identifies whether this is a final method	bool
ATTR_IS_INSTANTIABLE_METHOD	Identifies whether this is an instantiable method	bool
ATTR_IS_OVERRIDING_METHOD	Identifies whether this is an overriding method	bool

## Collection Attributes

A parameter for a collection type (type PTYPE\_COLL) has the attributes described in [Table 6–10](#).

**Table 6–10 Attributes that Belong to Collection Types**

Attribute	Description	Attribute Data Type
ATTR_DATA_SIZE	Maximum size of the type attribute. This length is returned in bytes and not characters for strings and raws. Returns 22 for NUMBER.	int
ATTR_TYPECODE	Typecode; refer to <a href="#">Notes on Types and Attributes</a> on page 6-1.	int
ATTR_DATA_TYPE	The data type of the type attribute; refer to <a href="#">Notes on Types and Attributes</a> on page 6-1.	int
ATTR_NUM_ELEMENTS	Number of elements in an array; only valid for collections that are arrays.	unsigned int
ATTR_NAME	A pointer to a string that is the type attribute name	string
ATTR_PRECISION	Precision of numeric type attributes. If the precision is nonzero and scale is $-127$ , then it is a FLOAT; otherwise a NUMBER( <i>p</i> , <i>s</i> ). If precision is 0, then NUMBER( <i>p</i> , <i>s</i> ) can be represented simply as NUMBER.	int
ATTR_SCALE	Scale of numeric type attributes. If the precision is nonzero and scale is $-127$ , then it is a FLOAT; otherwise a NUMBER( <i>p</i> , <i>s</i> ). If precision is 0, then NUMBER( <i>p</i> , <i>s</i> ) can be represented simply as NUMBER.	int



**Table 6–10 (Cont.) Attributes that Belong to Collection Types**

Attribute	Description	Attribute Data Type
ATTR_TYPE_NAME	String that is the type name. The returned value will contain the type name if the data type is <code>SQLT_NTY</code> or <code>SQLT_REF</code> . If the data type is <code>SQLT_NTY</code> , then the name of the named data type's type is returned. If the data type is <code>SQLT_REF</code> , then the type name of the named data type pointed to by the <code>REF</code> is returned	string
ATTR_SCHEMA_NAME	String with the schema name under which the type has been created	string
ATTR_REF_TDO	Returns the in memory <code>REF</code> of the <code>TDO</code> for the type.	RefAny
ATTR_CHARSET_ID	Typecode; refer to <a href="#">Notes on Types and Attributes</a> on page 6-1.	int
ATTR_CHARSET_FORM	The data type of the type attribute; refer to <a href="#">Notes on Types and Attributes</a> on page 6-1.	int

## Synonym Attributes

A parameter for a synonym (type `PTYPE_SYN`) has the attributes described in [Table 6–11](#).

**Table 6–11 Attributes that Belong to Synonyms**

Attribute	Description	Attribute Data Type
ATTR_OBJID	Object ID	unsigned int
ATTR_SCHEMA_NAME	Null-terminated string containing the schema name of the synonym translation	string
ATTR_NAME	Null-terminated string containing the object name of the synonym translation	string
ATTR_LINK	Null-terminated string containing the database link name of the synonym translation	string

## Sequence Attributes

A parameter for a sequence (type `PTYPE_SEQ`) has the attributes described in [Table 6–12](#).

**Table 6–12 Attributes that Belong to Sequences**

Attribute	Description	Attribute Data Type
ATTR_OBJID	Object ID	unsigned int
ATTR_MIN	Minimum value (in Oracle number format)	Number
ATTR_MAX	Maximum value (in Oracle number format)	Number
ATTR_INCR	Increment (in Oracle number format)	Number
ATTR_CACHE	Number of sequence numbers cached; zero if the sequence is not a cached sequence (in Oracle number format)	Number
ATTR_ORDER	Identifies whether the sequence is ordered	bool
ATTR_HW_MARK	High-water mark (in Oracle number format)	Number

## Column Attributes

A parameter for a column of a table or view (type `PTYPE_COL`) has the attributes described in [Table 6–13](#).

**Table 6–13 Attributes that Belong to Columns of Tables or Views**

Attribute	Description	Attribute Data Type
ATTR_DATA_SIZE	Column length in codepoints. The number of codepoints allowed in the column.	int
ATTR_DATA_TYPE	Type of length semantics of the column. Valid values are 0 for byte-length semantics and 1 for codepoint-length semantics.	int
ATTR_NAME	Maximum size of the column. This length is returned in bytes and not characters for strings and raws. Returns 22 for NUMBER.	string
ATTR_PRECISION	The data type of the column; refer to <a href="#">Notes on Types and Attributes</a> on page 6-1.	int
ATTR_SCALE	Pointer to a string that is the column name	int
ATTR_IS_NULL	Returns TRUE if the attribute is NULL; FALSE otherwise.	bool
ATTR_TYPE_NAME	Scale of numeric columns. If the precision is nonzero and scale is -127, then it is a FLOAT; otherwise a NUMBER(p, s). If precision is 0, then NUMBER(p, s) can be represented simply as NUMBER.	string
ATTR_SCHEMA_NAME	Returns 0 if null values are not permitted for the column	string
ATTR_REF_TDO	Returns a string that is the type name. The returned value will contain the type name if the data type is SQLT_NTY or SQLT_REF. If the data type is SQLT_NTY, then the name of the named data type's type is returned. If the data type is SQLT_REF, then the type name of the named data type pointed to by the REF is returned.	RefAny
ATTR_CHARSET_ID	Returns a string with the schema name under which the type has been created.	int
ATTR_CHARSET_FORM	The REF of the TDO for the type, if the column type is an object type	int

## Argument and Result Attributes

A parameter for an argument or a procedure or function type (type PTYPE\_ARG), for a type method argument (type PTYPE\_TYPE\_ARG), or for method results (type PTYPE\_TYPE\_RESULT) has the attributes described in [Table 6–14](#).

**Table 6–14 Attributes that Belong to Arguments / Results**

Attribute	Description	Attribute Data Type
ATTR_NAME	Returns a pointer to a string which is the argument name	string
ATTR_POSITION	Position of the argument in the argument list. Always returns 0.	int
ATTR_TYPECODE	Typecode; refer to <a href="#">Notes on Types and Attributes</a> on page 6-1.	int
ATTR_DATA_TYPE	Data type of the argument; refer to <a href="#">Notes on Types and Attributes</a> on page 6-1.	int
ATTR_DATA_SIZE	Size of the data type of the argument. This length is returned in bytes and not characters for strings and raws. Returns 22 for NUMBER.	int
ATTR_PRECISION	Precision of numeric arguments. If the precision is nonzero and scale is -127, then it is a FLOAT; otherwise a NUMBER(p, s). If precision is 0, then NUMBER(p, s) can be represented simply as NUMBER.	int

**Table 6–14 (Cont.) Attributes that Belong to Arguments / Results**

Attribute	Description	Attribute Data Type
ATTR_SCALE	Scale of numeric arguments. If the precision is nonzero and scale is -127, then it is a <code>FLOAT</code> ; otherwise a <code>NUMBER(p, s)</code> . If precision is 0, then <code>NUMBER(p, s)</code> can be represented simply as <code>NUMBER</code> .	<code>int</code>
ATTR_LEVEL	Data type levels. This attribute always returns 0.	<code>int</code>
ATTR_HAS_DEFAULT	Indicates whether an argument has a default	<code>int</code>
ATTR_LIST_ARGUMENTS	The list of arguments at the next level (when the argument is of a record or table type)	<code>vector&lt;MetaData&gt;</code>
ATTR_IOMODE	Indicates the argument mode; valid values are: <ul style="list-style-type: none"> <li>▪ 0 for <code>IN</code> (<code>OCCI_TYPEPARAM_IN</code>)</li> <li>▪ 1 for <code>OUT</code> (<code>OCCI_TYPEPARAM_OUT</code>)</li> <li>▪ 2 for <code>IN/OUT</code> (<code>OCCI_TYPEPARAM_INOUT</code>)</li> </ul>	<code>int</code>
ATTR_RADIX	Returns a radix (if number type)	<code>int</code>
ATTR_IS_NULL	Returns <code>FALSE</code> if <code>NULL</code> values are not permitted for the column.	<code>bool</code>
ATTR_TYPE_NAME	Returns a string that is the type name, or the package name in the case of package local types. The returned value contains the type name if the data type is <code>SQLT_NTY</code> or <code>SQLT_REF</code> . If the data type is <code>SQLT_NTY</code> , then the name of the named data type's type is returned. If the data type is <code>SQLT_REF</code> , then the type name of the named data type pointed to by the <code>REF</code> is returned.	<code>string</code>
ATTR_SCHEMA_NAME	For <code>SQLT_NTY</code> or <code>SQLT_REF</code> , returns a string with the schema name under which the type was created, or under which the package was created in the case of package local types	<code>string</code>
ATTR_SUB_NAME	For <code>SQLT_NTY</code> or <code>SQLT_REF</code> , returns a string with the type name, in the case of package local types	<code>string</code>
ATTR_LINK	For <code>SQLT_NTY</code> or <code>SQLT_REF</code> , returns a string with the database link name of the database on which the type exists. This can happen only in the case of package local types, when the package is remote.	<code>string</code>
ATTR_REF_TDO	Returns the <code>REF</code> of the <code>TDO</code> for the type, if the argument type is an object	<code>RefAny</code>
ATTR_CHARSET_ID	Returns the character set ID if the argument is of a string or character type	<code>int</code>
ATTR_CHARSET_FORM	Returns the character set form if the argument is of a string or character type	<code>int</code>

## List Attributes

A list type of attribute can be described for all the elements in the list. In case of a function argument list, position 0 has a parameter for return values (`P_TYPE_ARG`).

The list is described iteratively for all the elements. The results are stored in a C++ `vector<MetaData>`. Call the `getVector()` method to describe list type of attributes. Table 6–15 displays the list attributes.

**Table 6–15 Values for ATTR\_LIST\_TYPE**

Possible Values	Description
ATTR_LIST_COLUMNS	Column list
ATTR_LIST_ARGUMENTS	Procedure or function arguments list

**Table 6–15 (Cont.) Values for ATTR\_LIST\_TYPE**

Possible Values	Description
ATTR_LIST_SUBPROGRAMS	Subprogram list
ATTR_LIST_TYPE_ATTRIBUTES	Type attribute list
ATTR_LIST_TYPE_METHODS	Type method list
ATTR_LIST_OBJECTS	Object list within a schema
ATTR_LIST_SCHEMAS	Schema list within a database

## Schema Attributes

A parameter for a schema type (type PTYPE\_SCHEMA) has the attributes described in [Table 6–16](#).

**Table 6–16 Attributes Specific to Schemas**

Attribute	Description	Attribute Data Type
ATTR_LIST_OBJECTS	List of objects in the schema	string

## Database Attributes

A parameter for a database (type PTYPE\_DATABASE) has the attributes described in [Table 6–17](#).

**Table 6–17 Attributes Specific to Databases**

Attribute	Description	Attribute Data Type
ATTR_VERSION	Database version	string
ATTR_CHARSET_ID	Database character set ID from the server handle	int
ATTR_NCHARSET_ID	Database native character set ID from the server handle	int
ATTR_LIST_SCHEMAS	List of schemas (type PTYPE_SCHEMA) in the database	vector<MetaData>
ATTR_MAX_PROC_LEN	Maximum length of a procedure name	unsigned int
ATTR_MAX_COLUMN_LEN	Maximum length of a column name	unsigned int
ATTR_CURSOR_COMMIT_BEHAVIOR	How a COMMIT operation affects cursors and prepared statements in the database; values are: <ul style="list-style-type: none"> <li>▪ OCCI_CURSOR_OPEN for preserving cursor state as before the commit operation</li> <li>▪ OCCI_CURSOR_CLOSED for cursors that are closed on COMMIT, although the application can once again execute the statement without preparing it again</li> </ul>	int
ATTR_MAX_CATALOG_NAMELEN	Maximum length of a catalog (database) name	int
ATTR_CATALOG_LOCATION	Position of the catalog in a qualified table; values are: <ul style="list-style-type: none"> <li>▪ OCCI_CL_START</li> <li>▪ OCCI_CL_END</li> </ul>	int
ATTR_SAVEPOINT_SUPPORT	Identifies whether the database supports savepoints; values are: <ul style="list-style-type: none"> <li>▪ OCCI_SP_SUPPORTED</li> <li>▪ OCCI_SP_UNSUPPORTED</li> </ul>	int

**Table 6–17 (Cont.) Attributes Specific to Databases**

<b>Attribute</b>	<b>Description</b>	<b>Attribute Data Type</b>
ATTR_NOWAIT_SUPPORT	Identifies whether the database supports the nowait clause; values are: <ul style="list-style-type: none"><li>■ OCCI_NW_SUPPORTED</li><li>■ OCCI_NW_UNSUPPORTED</li></ul>	int
ATTR_AUTOCOMMIT_DDL	Identifies whether the autocommit mode is required for DDL statements; values are: <ul style="list-style-type: none"><li>■ OCCI_AC_DDL</li><li>■ OCCI_NO_AC_DDL</li></ul>	int
ATTR_LOCKING_MODE	Locking mode for the database; values are: <ul style="list-style-type: none"><li>■ OCCI_LOCK_IMMEDIATE</li><li>■ OCCI_LOCK_DELAYED</li></ul>	int



---

---

## Programming with LOBs

This chapter provides an overview of LOBs and their use in OCCI.

This chapter contains these topics:

- [Overview of LOBs](#)
- [Creating LOBs in OCCI Applications](#)
- [Restricting the Opening and Closing of LOBs](#)
- [Reading and Writing LOBs](#)
- [Using Objects with LOB Attributes](#)
- [Using SecureFiles](#)

**See also:** *Oracle Database SecureFiles and Large Objects Developer's Guide* for extensive information about LOBs

### Overview of LOBs

Oracle C++ Call Interface includes classes and methods for performing operations on large objects, LOBs. LOBs are either internal or external depending on their location with respect to the database.

### Introducing Internal LOBs

Internal LOBs are stored inside database tablespaces in a way that optimizes space and enables efficient access. Internal LOBs use copy semantics and participate in the transactional model of the server. You can recover internal LOBs in the event of transaction or media failure, and any changes to an internal LOB value can be committed or rolled back. There are three SQL data types for defining instances of internal LOBs:

- **BLOB:** A LOB whose value is composed of unstructured binary (raw) data
- **CLOB:** A LOB whose value is composed of character data that corresponds to the database character set defined for the Oracle database
- **NCLOB:** A LOB whose value is composed of character data that corresponds to the national character set defined for the Oracle database

The copy semantics for LOBs dictate that when you insert or update a LOB with a LOB from another row in the same table, both the LOB locator and the LOB value are copied. In other words, each row will have a copy of the LOB value.

## Introducing External LOBs

BFILES are large binary (raw) data objects data stored in operating system files outside database tablespaces; therefore, they are referred to as "external" LOBs. These files use reference semantics, where only the locator for the LOB is reproduced when inserting or updating in the same table. Apart from conventional secondary storage devices such as hard disks, BFILES may also be located on tertiary block storage devices such as CD-ROMs, PhotoCDs and DVDs. The BFILE data type allows read-only byte stream access to large files on the file system of the database server. Oracle can access BFILES if the underlying server operating system supports stream mode access to these files.

External LOBs do not participate in transactions. Any support for integrity and durability must be provided by the underlying file and operating systems. An external LOB must reside on a single device; it may not be striped across a disk array.

## Storing LOBs

The size of the LOB value, among other things, dictates where it is stored. The LOB value is either stored inline with the row data or outside the row.

- **Locator storage:** a LOB locator, a pointer to the actual location of the LOB value, is stored inline with the row data and indicates where the LOB value is stored.

For internal LOBs, the LOB column stores a locator to the LOB value stored in a database tablespace. Each internal LOB column and attribute for a particular row has its own unique LOB locator and a distinct copy of the LOB value stored in the database tablespace.

For external LOBs, the LOB column stores a locator to the external operating system file that houses the BFILE. Each external LOB column and attribute for a given row has its own BFILE locator. However, two different rows can contain a BFILE locator that points to the same operating system file.

- **Inline storage:** Data stored in a LOB is termed the LOB value. The value of an internal LOB may or may not be stored inline with the other row data. If you do not set `DISABLE STORAGE IN ROW`, and if the internal LOB value is less than approximately 4,000 bytes, then the value is stored inline. Otherwise, it is stored outside the row.

Since LOBs are intended to be large objects, inline storage will only be relevant if your application mixes small and large LOBs. The LOB value is automatically moved out of the row once it extends beyond approximately 4,000 bytes.

## Creating LOBs in OCCI Applications

Follow these steps to use LOBs in your application:

- Initialize a new LOB locator in the database.
- Assign a value to the LOB. In case of BFILES, assign a reference to a valid external file.
- To access and manipulate lob, see the OCCI classes that implement the methods for using LOBs in an application. All are detailed in [Chapter 13, "OCCI Application Programming Interface"](#):
  - [Bfile Class](#) on page 13-20 contains the APIs for BFILESs, as summarized in [Table 13-7](#)
  - [Blob Class](#) on page 13-26 contains the APIs for BLOBs, as summarized in [Table 13-8](#)



- [Clob Class](#) on page 13-37 contains the APIs for CLOBs and NCLOBs, as summarized in [Table 13-10](#)
- Whenever you want to modify an internal LOB column or attribute using write, copy, trim, and similar operations, you must lock the row that contains the target LOB. Use a `SELECT . . . FOR UPDATE` statement to select the LOB locator.
- A transaction must be open before a LOB write command succeeds. This means that you must write the data before committing a transaction (since `COMMIT` closes the transaction). Otherwise, you must lock the row again by reissuing the `SELECT . . . FOR UPDATE` statement. Each of the LOB class implementations in OCCI have `open()` and `close()` methods. To check whether a LOB is already open, call the `isOpen()` method of the class.
- The methods `open()`, `close()` and `isOpen()` should also be used to mark the beginning and end of a series of LOB operations. Whenever a LOB modification is made, it triggers updates on extensible indexes. If these modifications are made within `open() . . . close()` code blocks, the individual triggers are disabled until after the `close()` call, and then are issued all at once. This enables the efficient processing of maintenance operations, such as updating indexes, when the LOBs are closed. However, this also means that extensive indexes are not valid during the execution of the `open() . . . close()` code block.

Note that for internal LOBs, the concept of openness is associated with the LOB and not the LOB locator. The LOB locator does not store any information about whether the LOB to which it refers is open. It is possible for more than one LOB locator to point to the same open LOB. However, for external LOBs, openness is associated with a specific external LOB locator. Therefore, more than one `open()` call can be made on the same BFILE using different external LOB locators.

## Restricting the Opening and Closing of LOBs

The definition of a transaction within which an open LOB value must be closed is one of the following:

- Between `SET TRANSACTION` and `COMMIT`
- Between `DATA MODIFYING DML` and `COMMIT`
- Between `SELECT . . . FOR UPDATE` and `COMMIT`
- Within an autonomous transaction block

The LOB opening and closing mechanism has the following restrictions:

- An application must close all previously opened LOBs before committing a transaction. Failing to do so results in an error. If a transaction is rolled back, then all open LOBs are discarded along with the changes made, so associated triggers are not fired.
- While there is no limit to the number of open internal LOBs, there is a limit on the number of open files. Note that assigning an already opened locator to another locator does not count as opening a new LOB.
- It is an error to open or close the same internal LOB twice within the same transaction, either with different locators or with the same locator.
- It is an error to close a LOB that has not been opened.

## Reading and Writing LOBs

There are two general methods for reading and writing LOBs: non-streamed, and streamed.

### Reading LOBs

[Example 7-1](#) illustrates how to get data from a non-NULL internal LOB, using the a non-streamed method. This method requires that you keep track of the read offset and the amount remaining to be read, and pass these values to the `read()` method.

#### **Example 7-1 How to Read Non-Streamed BLOBs**

```
ResultSet *rset=stmt->executeQuery("SELECT ad_composite FROM print_media
                                   WHERE product_id=6666");
while(rset->next())
{
    Blob blob=rset->getBlob(1);
    if(blob.isNull())
        cerr <<"Null Blob"<<endl;
    else
    {
        blob.open(OCCI_LOB_READONLY);

        const unsigned int BUFSIZE=100;
        char buffer[BUFSIZE];
        unsigned int readAmt=BUFSIZE;
        unsigned int offset=1;

        //reading readAmt bytes from offset 1
        blob.read(readAmt,buffer,BUFSIZE,offset);

        //process information in buffer
        ...
        blob.close();
    }
}
stmt->closeResultSet(rset);
```

[Example 7-2](#) is similar as it demonstrates how to read data from a BFILE, where the BFILE locator is not NULL, by using a non-streamed read.

#### **Example 7-2 How to Read Non-Streamed BFILES**

```
ResultSet *rset=stmt->executeQuery("SELECT ad_graphic FROM print_media
                                   WHERE product_id=6666");
while(rset->next())
{
    Bfile file=rset->getBfile(1);
    if(bfile.isNull())
        cerr <<"Null Bfile"<<endl;
    else
    {
        //display the directory alias and the file name of the BFILE
        cout <<"File Name:"<<bfile.GetFileName()<<endl;
        cout <<"Directory Alias:"<<bfile.getDirAlias()<<endl;

        if(bfile.fileExists())
        {
            unsigned int length=bfile.length();
```

```

        char *buffer=new char[length];
        bfile.read(length, buffer, length, 1);
        //read all the contents of the BFILE into buffer, then process
        ...
        delete[] buffer;
    }
    else
        cerr <<"File does not exist"<<endl;
}
}
stmt->closeResultSet(rset);

```

In contrast to [Example 7-1](#) and [Example 7-2](#), the streamed reading demonstrated in [Example 7-3](#) on a non-NULL BLOB does not require keeping track of the offset.

### **Example 7-3 How to Read Streamed BLOBs**

```

ResultSet *rset=stmt->executeQuery("SELECT ad_composite FROM print_media
                                   WHERE product_id=6666");
while(rset->next())
{
    Blob blob=rset->getBlob(1);
    if(blob.isNull())
        cerr <<"Null Blob"<<endl;
    else
    {
        Stream *instream=blob.getStream(1,0);
        //reading from offset 1 to the end of the BLOB

        unsigned int size=blob.getChunkSize();
        char *buffer=new char[size];

        while((unsigned int length=instream->readBuffer(buffer,size))!=-1)
        {
            //process "length" bytes read into buffer
            ...
        }
        delete[] buffer;
        blob.closeStream(instream);
    }
}
stmt->closeResultSet(rset);

```

## Writing LOBs

[Example 7-4](#) demonstrates how to write data to an internal non-NULL LOB by using a non-streamed write. The `writeChunk()` method is enclosed by the `open()` and `close()` methods; it operates on a LOB that is currently open and ensures that triggers do not fire for every chunk read. The `write()` method can be used in place of the `writeChunk()` method; however, the `write()` method implicitly opens and closes the LOB.

### **Example 7-4 How to Write Non-Streamed BLOBs**

```

ResultSet *rset=stmt->executeQuery("SELECT ad_composite FROM print_media
                                   WHERE product_id=6666 FOR UPDATE");
while(rset->next())
{
    Blob blob=rset->getBlob(1);
    if(blob.isNull())

```

```
        cerr <<"Null Blob"<<endl;
    else
    {
        blob.open(OCCI_LOB_READWRITE);

        const unsigned int BUFSIZE=100;
        char buffer[BUFSIZE];
        unsigned int writeAmt=BUFSIZE;
        unsigned int offset=1;

        //writing writeAmt bytes from offset 1
        //contents of buffer are replaced after each writeChunk(),
        //typically with an fread()
        while(<fread "BUFSIZE" bytes into buffer succeeds>)
        {
            blob.writeChunk(writeAmt, buffer, BUFSIZE, offset);
            offset += writeAmt;
        }
        blob.writeChunk(<remaining amt>, buffer, BUFSIZE, offset);

        blob.close();
    }
}
stmt->closeResultSet(rset);
conn->commit();
```

**Example 7-5** demonstrates how to write data to an internal LOB that is already populated by using a streamed write.

#### **Example 7-5 How to Write Streamed BLOBs**

```
ResultSet *rset=stmt->executeQuery("SELECT ad_composite FROM print_media
                                   WHERE product_id=6666 FOR UPDATE");
while(rset->next())
{
    Blob blob=rset->getBlob(1);
    if(blob.isNull())
        cerr <<"Null Blob"<<endl;
    else
    {
        char buffer[BUFSIZE];
        Stream *ostream=blob.getOutputStream(1,0);

        //writing from buffer beginning at offset 1 until
        //a writeLastBuffer() method is issued.
        //contents of buffer are replaced after each writeBuffer(),
        //typically with an fread()
        while(<fread "BUFSIZE" bytes into buffer succeeds>)
            ostream->writeBuffer(buffer,BUFSIZE);
        ostream->writeLastBuffer(buffer,<remaining amt>);
        blob.closeStream(ostream);
    }
}
stmt->closeResultSet(rset);
conn->commit();
```

## **Enhancing the Performance of LOB Reads and Writes**

Reading and writing of internal LOBs can be improved by using either `getChunkSize()` method.

## Using the `getChunkSize()` Method

The `getChunkSize()` method returns the usable chunk size in bytes for BLOBs, and in characters for CLOBs and NCLOBs. Performance improves when a read or a write begins on a multiple of the usable chunk size, and the request size is also a multiple of the usable chunk size. You can specify the chunk size for a LOB column when you create a table that contains the LOB.

Calling the `getChunkSize()` method returns the usable chunk size of the LOB. An application can batch a series of write operations until an entire chunk can be written, rather than issuing multiple LOB write calls that operate on the same chunk

To read through the end of a LOB, use the `read()` method with an amount of 4 GB. This avoids the round-trip involved with first calling the `getLength()` method because the `read()` method with an amount of 4 GB reads until the end of the LOB is reached.

For LOBs that store variable width characters, the `GetChunkSize()` method returns the number of Unicode characters that fit in a LOB chunk.

## Updating LOBs

To update a value of a LOB in the database, you need to assign the new value to the lob, execute a SQL UPDATE command in the database, and then commit the transaction. [Example 7-6](#) demonstrates how to update an existing CLOB (in this case, by setting it to empty), while [Example 7-7](#) demonstrates how to update a BFILE.

### Example 7-6 Updating a CLOB Value

```
Clob clob(conn);
clob.setEmpty();
stmt->setSQL("UPDATE print_media SET ad_composite = :1
            WHERE product_id=6666");
stmt->setClob(1, clob);
stmt->executeUpdate();
conn->commit();
```

### Example 7-7 Updating a BFILE Value

```
Bfile bfile(conn);
bfile.setName("MEDIA_DIR", "img1.jpg");
stmt->setSQL("UPDATE print_media SET ad_graphic = :1
            WHERE product_id=6666");
stmt->setBfile(1, bfile);
stmt->executeUpdate();
conn->commit();
```

## Reading and Writing Multiple LOBs

As of Oracle Database 10g Release 2, OCCI has new interfaces that enhance application performance while reading and writing multiple LOBs, such as `Bfiles`, `Blobs`, `Clobs` and `NClobs`.

These interfaces have several advantages over the standard methods for reading and writing a single LOB at a time:

- Reading and writing multiple LOBs through OCCI in a single server round-trip improves performance by decreasing I/O time between the application and the back end.

- The new APIs provide support for LOBs that are larger than the previous limit of 4 GB. The new interfaces accept the `oraub8` data type for amount, offsets, buffer and length parameters. These parameters are mapped to the appropriate 64-bit native data type, which is determined by the compiler and the operating system.
- For `Clob`-related methods, the user can specify the data amount read or written in terms of character counts or byte counts.

New APIs for this features are described in [Chapter 13, "OCI Application Programming Interface"](#), section on [Connection Class](#), and include [readVectorOfBfiles\(\)](#) on page 13-55, [readVectorOfBlobs\(\)](#) on page 13-56, [readVectorOfClobs\(\)](#) on page 13-56 (overloaded to support general character sets, and the UTF16 character set in particular), [writeVectorOfBlobs\(\)](#) on page 13-60, and [writeVectorOfClobs\(\)](#) on page 13-60 (overloaded to support general character sets, and the UTF16 character set in particular).

### Using the Interfaces for Reading and Writing Multiple LOBs

Each of the `readVectorOfxxx()` and `writeVectorOfxxx()` interface uses the following parameters:

- `conn`, a `Connection` class object
- `vec`, a vector of LOB objects: `Bfile`, `Blob`, or `Clob`
- `byteAmts`, array of amounts, in bytes, for reading or writing
- `charAmts`, array of amounts, in characters, for reading or writing (only applicable for `Clobs` and `NClobs`)
- `offsets`, array of offsets, in bytes for `Bfiles` and `Blobs`, in characters for `Clobs`)
- `buffers`, array of buffer pointers
- `bufferLengths`, array of buffer lengths.

If there are errors in either reading or writing of one of the LOBs in the vector, the whole operation is cancelled. The `byteAmts` or `charAmts` parameters should be checked to determine the actual number of bytes or characters read or written.

## Using Objects with LOB Attributes

An OCI application can use the operator `new()` to create a persistent object with a LOB attribute. By default, all LOB attributes are constructed by using the default constructor, and are initialized to `NULL`.

[Example 7-8](#) demonstrates how to create and use persistent objects with internal LOB attributes. [Example 7-9](#) demonstrates how to create and use persistent objects with external LOB attributes.

### **Example 7-8 How to Use a Persistent Object with a BLOB Attribute**

1. Create a persistent object with a BLOB attribute:

```
Person *p=new(conn, "PERSON_TAB")Person();
p->imgBlob = Blob(conn);
```

2. Either initialize the `Blob` object to empty:

```
p->imgBlob.setEmpty();
```

Or set it to some existing value

3. Mark the Blob object as dirty:

```
p->markModified();
```

4. Flush the object:

```
p->flush();
```

5. Repin the object after obtaining a REF to it, thereby retrieving a refreshed version of the object from the database and acquiring an initialized LOB:

```
Ref<Person> r = p->getRef();
delete p;
p = r.ptr();
```

6. Write the data:

```
p->imgBlob.write( ... );
```

### **Example 7–9 How to Use a Persistent Object with a BFILE Attribute**

1. Create a persistent object with a BFILE attribute:

```
Person *p=new(conn, "PERSON_TAB") Person();
p->imgBFile = BFile(conn);
```

2. Initialize the Bfile object:

```
p->setName(directory_alias, file_name);
```

3. Mark the Bfile object as dirty:

```
p->markModified();
```

4. Flush the object:

```
p->flush();
```

5. Read the data:

```
p->imgBfile.read( ... );
```

## Using SecureFiles

Starting with Oracle Database 11g Release 1, SecureFiles add powerful new features for LOB compression, encryption, and deduplication.

**See Also:** *Oracle Database SecureFiles and Large Objects Developer's Guide*

## Using SecureFile Compression

SecureFile compression enables server-side compression of LOB data, which is transparent to the application. Using SecureFile compression saves storage space with minimal impact on reading and updating performance for SecureFile data.

## Using SecureFile Encryption

SecureFile encryption introduces a new encryption facility for LOB data and extends Transparent Data Encryption by enabling efficient random read and write access to the of the encrypted SecureFile.

## Using SecureFile Deduplication

SecureFile deduplication enables the Oracle Database to automatically detect duplicate LOB data, and to conserve space by storing a single copy of the LOB.

## Combining SecureFile Compression, Encryption, and Deduplication

You are allowed to combine compression, encryption and deduplication in any combination. Oracle Database will apply these features according to the following rules:

- Deduplicate detection, if enabled, will be performed before compression and encryption. This prevents the potentially unnecessary and expensive compression and encryption operations on SecureFiles that are already stored in a column.
- Compression will be performed before encryption, to allow for the highest possible compression ratios.

## SecureFile LOB Types and Constants

The following types for LOBs enable additional flexibility for compression, encryption, and deduplication of SecureFiles. [Table 7-1](#) lists options for the `LobOptionType`, while [Table 7-2](#) lists options for the `LobOptionValue`.

**Table 7-1 Values of Type `LobOptionType`**

Value	Description
<code>OCCI_LOB_OPT_COMPRESS</code>	Compression option type
<code>OCCI_LOB_OPT_ENCRYPT</code>	Encryption option type
<code>OCCI_LOB_OPT_DEDUPLICATE</code>	Deduplicate option type

**Table 7-2 Values of Type `LobOptionValue`**

Value	Description
<code>OCCI_LOB_COMPRESS_OFF</code>	Turns off LOB compression
<code>OCCI_LOB_COMPRESS_ON</code>	Turns on LOB compression
<code>OCCI_LOB_ENCRYPT_OFF</code>	Turns off LOB encryption
<code>OCCI_LOB_ENCRYPT_ON</code>	Turns on LOB encryption
<code>OCCI_LOB_DEDUPLICATE_OFF</code>	Turns off LOB deduplication
<code>OCCI_LOB_DEDUPLICATE_ON</code>	Turns off LOB deduplication



---

---

## Object Type Translator Utility

This chapter discusses the Object Type Translator (OTT) utility, which is used to map database object types, LOB types, and named collection types to C++ class declarations for use in OCCI applications.

This chapter contains these topics:

- [Overview of the Object Type Translator Utility](#)
- [Using the OTT Utility](#)
- [Creating Types in the Database](#)
- [Invoking the OTT Utility](#)
- [Using the INTYPE File](#)
- [OTT Utility Data Type Mappings](#)
- [Overview of the OUTTYPE File](#)
- [The OTT Utility and OCCI Applications](#)
- [Carrying Forward User Added Code](#)

**See Also:** `$ORACLE_HOME/rdbms/demo` for a complete code listing of the demonstration program used in this chapter and the class and method implementation generated by the OTT utility.

### Overview of the Object Type Translator Utility

The Object Type Translator (OTT) utility assists in the development of applications that make use of user-defined types in an Oracle database server.

Through the use of SQL `CREATE TYPE` statements, you can create object types. The definitions of these types are stored in the database and can be used in the creation of database tables. Once these tables are populated, an OCCI programmer can access objects stored in the tables.

An application that accesses object data must be able to represent the data in a host language format. This is accomplished by representing object types classes in C++.

You could code structures or classes manually to represent database object types, but this is time-consuming and error-prone. The OTT utility simplifies this step by automatically generating the appropriate classes for C++.

For OCCI, the application must include and link the following files:

- Include the header file containing the generated class declarations

- Include the header file containing the prototype for the function to register the mappings
- Link with the C++ source file containing the static methods to be called by OCCI while instantiating the objects
- Link with the file containing the function to register the mappings with the environment and call this function

## Using the OTT Utility

To translate database types to C++ representation, you must explicitly invoke the OTT utility. OCCI programmers must register the mappings with the environment. This function is generated by the OTT utility.

On most operating systems, the OTT utility is invoked on the command line. It takes as input an `INTYPE` file, and generates an `OUTTYPE` file, one or more C++ header files that contain the prototype information, and additional C++ method files that register generated mappings.

### **Example 8-1** How to Use the OTT Utility

The following command invokes the OTT utility and generates C++ classes. OTT attempts to connect with username `demouser`; the system prompts for the password.

```
ott userid=demouser intype=demoin.typ outtype=demoout.typ code=cpp
    hfile=demo.h cppfile=demo.cpp mapfile=RegisterMappings.cpp
```

OTT utility uses the `demoin.typ` file as the `INTYPE` file, and the `demoout.typ` file as the `OUTTYPE` file. The resulting declarations are output to the file `demo.h` in C++, specified by the `CODE=cpp` parameter, the method implementations written to the file `demo.cpp`, and the functions to register mappings is written to `RegisterMappings.cpp` with its prototype written to `RegisterMappings.h`.

**See Also:** [Extending C++ Classes](#) on page 8-27 for a complete C++ example

## Creating Types in the Database

The first step in using the OTT utility is to create object types or named collection types and store them in the database. This is accomplished through the use of the SQL `CREATE TYPE` statement.

### **Example 8-2** Object Creation Statements of the OTT Utility

```
CREATE TYPE FULL_NAME AS OBJECT (first_name CHAR(20), last_name CHAR(20));
CREATE TYPE ADDRESS AS OBJECT (state CHAR(20), zip CHAR(20));
CREATE TYPE ADDRESS_TAB AS VARRAY(3) OF REF ADDRESS;
CREATE TYPE PERSON AS OBJECT (id NUMBER, name FULL_NAME, curr_addr REF ADDRESS,
    prev_addr_1 ADDRESS_TAB) NOT FINAL;
CREATE TYPE STUDENT UNDER PERSON (school_name CHAR(20));
```

## Invoking the OTT Utility

After creating types in the database, the next step is to invoke the OTT utility.

## Specifying OTT Parameters

You can specify OTT parameters either on the command line or in a configuration file. Certain parameters can also be specified in the `INTYPE` file.

If you specify a parameter in more than one place, then its value on the command line takes precedence over its value in the `INTYPE` file. The value in the `INTYPE` file takes precedence over its value in a user-defined configuration file, which takes precedence over its value in the default configuration file.

Parameter precedence then is as follows:

1. OTT command line
2. Value in `INTYPE` file
3. User-defined configuration file
4. Default configuration file

For global options (that is, options on the command line or options at the beginning of the `INTYPE` file before any `TYPE` statements), the value on the command line overrides the value in the `INTYPE` file. (The options that can be specified globally in the `INTYPE` file are `CASE`, `INITFILE`, `INITFUNC`, `MAPFILE` and `MAPFUNC`, but not `HFILE` or `CPPFILE`.) Anything in the `INTYPE` file in a `TYPE` specification applies to a particular type only and overrides anything on the command line that would otherwise apply to the type. So if you enter `TYPE person HFILE=p.h`, then it applies to `person` only and overrides the `HFILE` on the command line. The statement is not considered a command line parameter.

### Setting Parameters on the Command Line

Parameters (also called options) set on the command line override any parameters or option set elsewhere.

### Setting Parameters in the INTYPE File

The `INTYPE` file gives a list of types for the OTT utility to translate.

The parameters `CASE`, `CPPFILE`, `HFILE`, `INITFILE`, `INITFUNC`, `MAPFILE`, and `MAPFUNC` can appear in the `INTYPE` file.

### Setting Parameters in the Configuration File

A configuration file is a text file that contains OTT parameters. Each nonblank line in the file contains one parameter, with its associated value or values. If more than one parameter is put on a line, then only the first one will be used. No blank space is allowed on any nonblank line of a configuration file.

A configuration file can be named on the command line. In addition, a default configuration file is always read. This default configuration file must always exist, but can be empty. The name of the default configuration file is `ottcfg.cfg`, and the location of the file is operating system-specific.

**See Also:** Your operating system-specific documentation for more information about the location of the default configuration file.

## Invoking the OTT Utility on the Command Line

On most platforms, the OTT utility is invoked on the command line. You can specify the input and output files and the database connection information at the command line, among other things.

**See Also:** Your operating system-specific documentation to see how to invoke the OTT utility on your operating system

### **Example 8–3 How to Invoke the OTT Utility to Generate C++ Classes**

OTT attempts to connect with username `demour`; the system prompts for the password.

```
ott userid=demour intype=demoin.typ outtype=demoout.typ code=cpp
  hfile=demo.h cppfile=demo.cpp mapfile=RegisterMappings.cpp
```

---

---

**Caution:** No spaces are permitted around the equals sign (=) on the OTT command line.

---

---

An OTT command line statement consists of the command OTT, followed by a list of OTT utility parameters.

The `HFILE` parameter is almost always used. If omitted, then `HFILE` must be specified individually for each type in the `INTYPE` file. If the OTT utility determines that a type not listed in the `INTYPE` file must be translated, then an error will be reported. Therefore, it is safe to omit the `HFILE` parameter only if the `INTYPE` file was previously generated as an OTT `OUTTYPE` file.

If the `INTYPE` file is omitted, then the entire schema will be translated. See the parameter descriptions in the following section for more information.

### **Elements Used on the OTT Command Line**

Elements used on the OTT command line are:

- OTT command that invokes the OTT utility. It must be the first item on the command line.
- [USERID](#) parameter on page 8-11
- [INTYPE](#) parameter on page 8-7
- [OUTTYPE](#) parameter on page 8-8.
- [CODE](#) parameter on page 8-6.
- [HFILE](#) parameter on page 8-7.
- [CPPFILE](#) parameter on page 8-6.
- [MAPFILE](#) parameter on page 8-7.

## **OTT Utility Parameters**

To generate C++ using the OTT utility, the `CODE` parameter must be set to `CODE=CPP`. Once `CODE=CPP` is specified, you are required to specify the `CPPFILE` and `MAPFILE` parameters to define the filenames for the method implementation file and the mappings registration function file. The name of the mapping function is derived by the OTT utility from the `MAPFILE` or you may specify the name with the `MAPFUNC` parameter. `ATTRACCESS` is also an optional parameter that can be specified to change the generated code. These parameters control the generation of C++ classes.

- Enter parameters on the OTT command line where `parameter` is the literal parameter string and `value` is a valid parameter setting. The literal parameter string is not case sensitive:

```
parameter=value
```

- Separate command line parameters by using either spaces or tabs.
- Parameters can also appear within a configuration file, but, in that case, no whitespace is permitted within a line, and each parameter must appear on a separate line. Additionally, the parameters `CASE`, `CPPFILE`, `HFILE`, `INITFILE`, `INTFUNC`, `MAPFILE`, and `MAPFUNC` can appear in the `INTYPE` file.

Table 8–1 lists all OTT Utility parameters:

**Table 8–1 Summary of OTT Utility Parameters**

Parameter	Description
<code>ATTRACCESS</code>	Specifies whether the access to type attributes will be <code>PROTECTED</code> or <code>PRIVATE</code> .
<code>CASE</code>	Affects the letter case of generated C++ identifiers
<code>CODE</code>	Specifies the target language for the translation. Use <code>CPP</code> .
<code>CONFIG</code>	Specifies the name of the OTT configuration file that lists commonly used parameter specifications.
<code>CPPFILE</code>	Specifies the name of the C++ source file into which the method implementations are written.
<code>ERRTYPE</code>	Specifies the name of the error message output file.
<code>HFILE</code>	Specifies the name of the C++ header file to which the generated C++ classes are written.
<code>INTYPE</code>	Specifies the name of the <code>INTYPE</code> file.
<code>MAPFILE</code>	Specifies the name of the mapping file and the corresponding header file generated by the OTT utility.
<code>MAPFUNC</code>	Specifies the name of the function used to register generated mappings.
<code>OUTTYPE</code>	Specifies the name of the <code>OUTTYPE</code> file.
<code>SCHEMA_NAMES</code>	Controls the qualifying the database name of a type from the default schema
<code>TRANSITIVE</code>	Indicates whether to translate type dependency that are not explicitly listed in the <code>INTYPE</code> .
<code>UNICODE</code>	Indicates whether the application should provide UTF16 support generate <code>UString</code> types.
<code>USE_MARKER</code>	Indicates whether OTT markers should be supported to carry forward user added cod
<code>USERID</code>	Specifies the database connection information that the OTT utility will use.

### **ATTRACCESS**

This parameter specifies access to type attributes:

- `PROTECTED` is the default.
- `PRIVATE` indicates that the OTT utility generates accessory and mutator methods for each type attribute, `getXXX()` and `setXXX()`.

### **CASE**

This parameter affects the letter case of generated C++ identifiers. The valid values of `CASE` are:

- `SAME` is the case of letters remains unchanged when converting database type and attribute names to C++ identifiers.
- `LOWER` indicates that all uppercase letters are converted to lowercase.
- `UPPER` indicates that all lowercase letters are converted to uppercase.
- `OPPOSITE` indicates that all uppercase letters are converted to lowercase, and all lowercase letters are converted to uppercase.

This parameter affects only those identifiers (attributes or types not explicitly listed) not mentioned in the `INTYPE` file. Case conversion takes place after a legal identifier has been generated.

---

---

**Note:** Case insensitive SQL identifiers not mentioned in the `INTYPE` file will appear in uppercase if `CASE=SAME`, and in lowercase if `CASE=OPPOSITE`. A SQL identifier is case insensitive if it was not quoted when it was declared.

---

---

## CODE

This parameter specifies the host language to be output by the OTT utility. `CODE=CPP` must be specified for the OTT utility to generate C++ code for OCCI applications.

## CONFIG

This parameter specifies the name of the OTT configuration file that lists commonly used parameter specifications. Parameter specifications are also read from a system configuration file found in an operating system-dependent location. All remaining parameter specifications must appear either on the command line or in the `INTYPE` file.

---

---

**Note:** The `CONFIG` parameter can only be specified on the OTT command line. It is not allowed in the `CONFIG` file.

---

---

## CPPFILE

This parameter specifies the name of the C++ source file that will contain the method implementations generated by the OTT utility. The methods generated in this file are called by OCCI while instantiating the objects and are not to be called directly in the an application.

This parameter is required under the following conditions:

- A type not mentioned in the `INTYPE` file must be generated and two or more `CPPFILES` are being generated. In this case, the unmentioned type goes in the `CPPFILE` specified on the command line.
- The `INTYPE` parameter is not specified, and you want the OTT utility to translate all the types in the schema.

This parameter is optional when the `CPPFILE` is specified for individual types in the `INTYPE` file.

## ERRTYPE

This parameter specifies the name of the error message output file. Information and error messages are sent to the standard output whether or not the `ERRTYPE` parameter is specified. Essentially, the `ERRTYPE` file is a copy of the `INTYPE` file with error

messages added. In most cases, an error message will include a pointer to the text that caused the error.

If the filename specified for the `ERRTYPE` parameter on the command line does not include an extension, a platform-specific extension such as `.TLS` or `.t1s` is added automatically.

## HFILE

This parameter specifies the name of the header (`.h`) file to be generated by the OTT utility. The `HFILE` specified on the command line contains the declarations of types that are mentioned in the `INTYPE` file but whose header files are not specified there.

This parameter is required unless the header file for each type is specified individually in the `INTYPE` file. This parameter is also required if a type not mentioned in the `INTYPE` file must be generated because other types require it, and these other types are declared in two or more different files.

If the filename specified for the `HFILE` parameter on the command line or in the `INTYPE` file does not include an extension, a platform-specific extension such as `.H` or `.h` is added automatically.

## INTYPE

This parameter specifies the name of the file from which to read the list of object type specifications. The OTT utility translates each type in the list. If the `INTYPE` parameter is not specified, all types in the user's schema will be translated.

If the filename specified for the `INTYPE` parameter on the command line does not include an extension, a platform-specific extension such as `.TYP` or `.typ` is automatically added.

`INTYPE=` may be omitted if `USERID` and `INTYPE` are the first two parameters, in that order, and `USERID=` is omitted.

The `INTYPE` file can be thought of as a makefile for type declarations. It lists the types for which C++ classes are needed.

**See Also:** ["Structure of the INTYPE File"](#) on page 8-14 for more information about the format of the `INTYPE` file

## MAPFILE

This parameter specifies the name of the mapping file (`XXX.cpp`) and corresponding header file (`XXX.h`) that are generated by the OTT utility. The `XXX.cpp` file contains the implementation of the functions to register the mappings, while the `XXX.h` file contains the prototype for the function.

This parameter may be specified either on the command line or in the `INTYPE` file.

## MAPFUNC

This parameter specifies the name of the function to be used to register the mappings generated by the OTT utility.

If this parameter is omitted, then the name of the function to register the mappings is derived from the filename specified in the `MAPFILE` parameter.

This parameter may be specified either on the command line or in the `INTYPE` file.

## OUTTYPE

This parameter specifies the name of the file into which the OTT utility writes type information for all the object data types it processes. This file includes all types explicitly named in the `INTYPE` file, and may include additional types that are translated because they are used in the declarations of other types that need to be translated. This file may be used as an `INTYPE` file in a future invocation of the OTT utility.

If the `INTYPE` and `OUTTYPE` parameters refer to the same file, then the new `INTYPE` information replaces the old information in the `INTYPE` file. This provides a convenient way for the same `INTYPE` file to be used repeatedly in the cycle of altering types, generating type declarations, editing source code, precompiling, compiling, and debugging.

If the filename specified for the `OUTTYPE` parameter on the command line or in the `INTYPE` file does not include an extension, a platform-specific extension such as `.TYP` or `.typ` is automatically added.

## SCHEMA\_NAMES

This parameter offers control in qualifying the database name of a type from the default schema that is named in the `OUTTYPE` file. The `OUTTYPE` file generated by the OTT utility contains information about the types processed by the OTT utility, including the type names. Valid values include:

- `ALWAYS` (default) indicates that all type names in the `OUTTYPE` file are qualified with a schema name.
- `IF_NEEDED` indicates that the type names in the `OUTTYPE` file that belong to the default schema are not qualified with a schema name. Type names belonging to other schemas are qualified with the schema name.
- `FROM_INTYPE` indicates that a type mentioned in the `INTYPE` file is qualified with a schema name in the `OUTTYPE` file only if it was qualified with a schema name in the `INTYPE` file. A type in the default schema that is not mentioned in the `INTYPE` file but generated because of type dependency is written with a schema name only if the first type encountered by the OTT utility that depends on it is also written with a schema name. However, a type that is not in the default schema to which the OTT utility is connected is always written with an explicit schema name.

The name of a type from a schema other than the default schema is always qualified with a schema name in the `OUTTYPE` file.

The schema name, or its absence, determines in which schema the type is found during program execution.

### **Example 8-4 How to use the SCHEMA\_NAMES Parameter in OTT Utility**

Consider an example where the `SCHEMA_NAMES` parameter is set to `FROM_INTYPE`, and the `INTYPE` file contains the following:

```
TYPE Person
TYPE joe.Dept
TYPE sam.Company
```

If the OTT utility and the application both connect to schema `joe`, then the application uses the same type (`joe.Person`) that the OTT utility uses. If the OTT utility connects to schema `joe` but the application connects to schema `mary`, then the application uses



the type `mary.Person`. This behavior is appropriate only if the same `CREATE TYPE Person` statement has been executed in schema `joe` and schema `mary`.

On the other hand, the application uses type `joe.Dept` regardless of which schema the application is connected to. If this is the behavior you want, then be sure to include schema names with your type names in the `INTYPE` file.

In some cases, the OTT utility translates a type that the user did not explicitly name. For example, consider the following SQL declarations:

```
CREATE TYPE Address AS OBJECT
(
  street   VARCHAR2(40),
  city     VARCHAR(30),
  state    CHAR(2),
  zip_code CHAR(10)
);

CREATE TYPE Person AS OBJECT
(
  name     CHAR(20),
  age      NUMBER,
  addr     ADDRESS
);
```

Suppose that the OTT utility connects to schema `joe`, `SCHEMA_NAMES=FROM_INTYPE` is specified, and the user's `INTYPE` files include either `TYPE Person` or `TYPE joe.Person`. The `INTYPE` file does not mention the type `joe.Address`, which is used as a nested object type in type `joe.Person`.

- If `TYPE Person` appears in the `INTYPE` file, then `TYPE Person` and `TYPE Address` appears in the `OUTTYPE` file.
- If `TYPE joe.Person` appears in the `INTYPE` file, then `TYPE joe.Person` and `TYPE joe.Address` appear in the `OUTTYPE` file.
- If the `joe.Address` type is embedded in several types translated by the OTT utility, but it is not explicitly mentioned in the `INTYPE` file, then the decision of whether to use a schema name is made the first time the OTT utility encounters the embedded `joe.Address` type. If, for some reason, the user wants type `joe.Address` to have a schema name but does not want type `Person` to have one, then you must explicitly request this in the `INTYPE` file: `TYPE joe.Address`.

In the usual case in which each type is declared in a single schema, it is safest for you to qualify all type names with schema names in the `INTYPE` file.

## TRANSITIVE

This parameter indicates whether type dependencies not explicitly listed in the `INTYPE` file are to be translated. Valid values are:

- `TRUE` (default): types needed by other types and not mentioned in the `INTYPE` file are generated
- `FALSE`: types not mentioned in the `INTYPE` file are not generated, even if they are used as attribute types of other generated types.

## UNICODE

This parameter specifies whether the application provides unicode (UTF16) support.

- NONE (default) --
- ALL -- All CHAR (CHAR/VARCHAR) and NCHAR (NCHAR/NVARCHAR2) type attributes are declared as UString type in the OTT generated C++ class files. The corresponding getXXX()/setXXX() return values or parameters are UString types. The generated persistent operator new would also take only UString arguments.

---

---

**Note:** This setting should be used when both the client character set and the national character set is UTF16.

---

---

- ONLYNCHAR -- Similar to the ALL option, but only NCHAR type attributes will be declared as UString.

---

---

**Note:** This setting should be used when the application sets only the Environment's national character set to UTF16.

---

---

#### **Example 8–5 How to Define a Schema for Unicode Support in OTT**

```
create type CitiesList as varray(100) of varchar2(100);

create type Country as object
( CNo Number(10),
  CName Varchar2(100),
  CNationalName NVarchar2(100),
  MainCities CitiesList);
```

#### **Example 8–6 How to Use UNICODE=ALL Parameter in OTT**

```
class Country : public oracle::occi::PObject
{
private:
    oracle::occi::Number CNO;
    oracle::occi::UString CNAME;
    oracle::occi::UString CNATIONALNAME;
    OCCI_STD_NAMESPACE::vector< oracle::occi::UString > MAINCITIES;

public:

    oracle::occi::Number getCno() const;
    void setCno(const oracle::occi::Number &value);

    oracle::occi::UString getCname() const;
    void setCname(const oracle::occi::UString &value);

    oracle::occi::UString getCnationalname() const;
    void setCnationalname(const oracle::occi::UString &value);

    OCCI_STD_NAMESPACE::vector< oracle::occi::UString >& getMaincities();
    const OCCI_STD_NAMESPACE::vector< oracle::occi::UString >&
        getMaincities() const;
    void setMaincities(const OCCI_STD_NAMESPACE::vector< oracle::occi::UString
        > &value);
    ...
}
```

**Example 8-7 How to Use UNICODE=ONLYCHAR Parameter in OTT**

```

class Country : public oracle::occi::PObject
{
    private:
        oracle::occi::Number CNO;
        oracle::occi::string CNAME;
        oracle::occi::UString CNATIONALNAME;
        OCCI_STD_NAMESPACE::vector< std::string > MAINCITIES;

    public:

        oracle::occi::Number getCno() const;
        void setCno(const oracle::occi::Number &value);

        oracle::occi::string getName() const;
        void setName(const OCCI_STD_NAMESPACE::string &value);

        oracle::occi::UString getCnationalname() const;
        void setCnationalname(const oracle::occi::UString &value);

        OCCI_STD_NAMESPACE::vector< OCCI_STD_NAMESPACE::string>&
            getMaincities();
        const OCCI_STD_NAMESPACE::vector< OCCI_STD_NAMESPACE::string >&
            getMaincities() const;
        void setMaincities(const OCCI_STD_NAMESPACE::vector
            < OCCI_STD_NAMESPACE::string > &value);
    ...
}

```

**USE\_MARKER**

This parameter indicates whether to support OTT markers for carrying forward user added code. Valid values are:

- FALSE (default) -- user added code will not be carried forward, even if the code is added between OTT\_USERCODE\_START and OTT\_USERCODE\_END markers.
- TRUE -- code added between the markers OTT\_USER\_CODESTART and OTT\_USERCODE\_END will be carried forward when the same file is generated again.

**USERID**

This parameter specifies the Oracle username and optional database name (Oracle Net database specification string). If the database name is omitted, the default database is assumed.

```
USERID=username[@db_name]
```

If this is the first parameter, then USERID= may be omitted as shown:

```
OTT username ...
```

Note that the system will prompt you for the password that corresponds to the user id.

This parameter is optional. If omitted, the OTT utility automatically attempts to connect to the default database as user *OPSS*username, where *username* is the user's operating system username.

## Where OTT Parameters Can Appear

Supply OTT parameters on the command line, in a CONFIG file named on the command line, or both. Some parameters are also allowed in the INTYPE file.

The OTT utility is invoked as follows:

```
OTT parameters
```

You can name a configuration file on the command line with the CONFIG parameter as follows:

```
CONFIG=filename
```

If you name this parameter on the command line, then additional parameters are read from the configuration file named *filename*.

In addition, parameters are also read from a default configuration file that resides in an operating system-dependent location. This file must exist, but can be empty. If you choose to enter data in the configuration file, note that no white space is allowed on a line and parameters must be entered one to a line.

If the OTT utility is executed without any arguments, then an online parameter reference is displayed.

The types for the OTT utility to translate are named in the file specified by the INTYPE parameter. The parameters CASE, CPPFILE, HFILE, INITFILE, INITFUNC, MAPFILE, and MAPFNC may also appear in the INTYPE file. OUTTYPE files generated by the OTT utility include the CASE parameter, and include the INITFILE, and INITFUNC parameters if an initialization file was generated or the MAPFILE and MAPFUNC parameters if C++ codes was generated. The OUTTYPE file, as well as the CPPFILE for C++, specifies the HFILE individually for each type.

The case of the OTT command is operating system-dependent.

## File Name Comparison Restriction

Currently, the OTT utility determines if two files are the same by comparing the filenames provided by the user either on the command line or in the INTYPE file. But one potential problem can occur when the OTT utility needs to know if two filenames refer to the same file. For example, if the OTT-generated file `foo.h` requires a type declaration written to `foo1.h`, and another type declaration written to `/private/smith/foo1.h`, then the OTT utility should generate one `#include` if the two files are the same, and two `#includes` if the files are different. In practice, though, it concludes that the two files are different, and generates two `#includes` as follows:

```
#ifndef FOO1_ORACLE
#include "foo1.h"
#endif
#ifndef FOO1_ORACLE
#include "/private/smith/foo1.h"
#endif
```

If `foo1.h` and `/private/smith/foo1.h` are different files, then only the first one will be included. If `foo1.h` and `/private/smith/foo1.h` are the same file, then a redundant `#include` will be written.

Therefore, if a file is mentioned several times on the command line or in the INTYPE file, then each mention of the file should use exactly the same filename.

## Using the INTYPE File

When you run the OTT utility, the INTYPE file tells the OTT utility which database types should be translated. The INTYPE file also controls the naming of the generated structures or classes. You can either create an INTYPE file or use the OUTTYPE file of a previous invocation of the OTT utility. If you do not use an INTYPE file, then all types in the schema to which the OTT utility connects are translated.

### Overview of the INTYPE File

#### **Example 8–8 How to Create a User Defined INTYPE File Using the OTT Utility**

```
CASE=LOWER
TYPE employee
    TRANSLATE SALARY$ AS salary
        DEPTNO AS department
TYPE ADDRESS
TYPE item
TYPE "Person"
TYPE PURCHASE_ORDER AS p_o
```

- In the first line, the CASE parameter indicates that generated C identifiers should be in lowercase. However, this CASE parameter is only applied to those identifiers that are not explicitly mentioned in the INTYPE file. Thus, `employee` and `ADDRESS` would always result in C structures `employee` and `ADDRESS`, respectively. The members of these structures are named in lowercase.
- The lines that begin with the TYPE keyword specify which types in the database should be translated. In this case, the `EMPLOYEE`, `ADDRESS`, `ITEM`, `PERSON`, and `PURCHASE_ORDER` types are set to be translated.
- The `TRANSLATE . . . AS` keywords specify that the name of an object attribute should be changed when the type is translated into a C structure. In this case, the `SALARY$` attribute of the `employee` type is translated to `salary`.
- The `AS` keyword in the final line specifies that the name of an object type should be changed when it is translated into a structure. In this case, the `purchase_order` database type is translated into a structure called `p_o`.

The OTT utility may need to translate additional types that are not listed in the INTYPE file. This is because the OTT utility analyzes the types in the INTYPE file for type dependencies before performing the translation, and it translates other types as necessary. For example, if the `ADDRESS` type were not listed in the INTYPE file, but the `Person` type had an attribute of type `ADDRESS`, then the OTT utility would still translate `ADDRESS` because it is required to define the `Person` type.

---



---

**Note:** To specify that the OTT utility should not generate required object types that are not specified in the INTYPE file, set `TRANSITIVE=FALSE`. The default is `TRANSITIVE=TRUE`.

---



---

A normal case insensitive SQL identifier can be spelled in any combination of uppercase and lowercase in the INTYPE file, and is not quoted.

Use quotation marks, such as `TYPE "Person"` to reference SQL identifiers that have been created in a case sensitive manner, for example, `CREATE TYPE "Person"`. A SQL identifier is case sensitive if it was quoted when it was declared. Quotation marks can also be used to refer to a SQL identifier that is an OTT-reserved word, for example,

TYPE "CASE". In this case, the quoted name must be in uppercase if the SQL identifier was created in a case insensitive manner, for example, CREATE TYPE Case. If an OTT-reserved word is used to refer to the name of a SQL identifier but is not quoted, then the OTT utility will report a syntax error in the INTYPE file.

**See Also:**

- ["Structure of the INTYPE File"](#) on page 8-14 for a more detailed specification of the structure of the INTYPE file and the available options.
- ["CASE"](#) on page 8-5 for further information regarding the CASE parameter

## Structure of the INTYPE File

The INTYPE and OUTTYPE files list the types translated by the OTT utility and provide all the information needed to determine how a type or attribute name is translated to a legal C or C++ identifier. These files contain one or more type specifications, and may also contain specifications of CASE, CPPFILE, HFILE, INITFILE, INITFUNC, MAPFILE, or MAPFUNC.

If the CASE, INITFILE, INITFUNC, MAPFILE, or MAPFUNC options are present, then they must precede any type specifications. If these options appear both on the command line and in the INTYPE file, then the value on the command line is used.

**See Also:** ["Overview of the OUTTYPE File"](#) on page 8-23 for an example of a simple user-defined INTYPE file and of the full OUTTYPE file that the OTT utility generates from it

### INTYPE File Type Specifications

A type specification in the INTYPE file names an object data type that is to be translated. The following is an example of a user-created INTYPE file:

```
TYPE employee
  TRANSLATE SALARY$ AS salary
  DEPTNO AS department
TYPE ADDRESS
TYPE PURCHASE_ORDER AS p_o
```

The structure of a type specification is as follows:

```
TYPE type_name
[GENERATE type_identifier]
[AS type_identifier]
[VERSION [=] version_string]
[HFILE [=] hfile_name]
[CPPFILE [=] cppfile_name]
[TRANSLATE{member_name [AS identifier]}...]
```

The type\_name syntax follows this form:

```
[schema_name.]type_name
```

In this syntax, *schema\_name* is the name of the schema that owns the given object data type, and *type\_name* is the name of the type. The default schema, if one is not specified, is that of the userID invoking the OTT utility. To use a specific schema, you must use *schema\_name*.

The components of the type specification are:

- *type\_name*: Name of the object data type.
- *type\_identifier*: C / C++ identifier used to represent the class. The GENERATE clause is used to specify the name of the class that the OTT utility generates. The AS clause specifies the name of the class that you write. The GENERATE clause is typically used to extend a class. The AS clause, when optionally used without the GENERATE clause, specifies the name of the C structure or the C++ class that represents the user-defined type.
- *version\_string*: Version string of the type that was used when the code was generated by the previous invocation of the OTT utility. The version string is generated by the OTT utility and written to the OUTTYPE file, which can later be used as the INTYPE file in later invocations of the OTT utility. The version string does not affect how the OTT utility operates, but can be used to select which version of the object data type is used in the running program.
- *hfile\_name*: Name of the header file into which the declarations of the corresponding class are written. If you omit the HFILE clause, then the file specified by the command line HFILE parameter is used.
- *cppfile\_name*: Name of the C++ source file into which the method implementations of the corresponding class is written. If you omit the CPPFILE clause, the file specified by the command line CPPFILE parameter is used.
- *member\_name*: Name of an attribute (data member) that is to be translated to the identifier.
- *identifier*: C / C++ identifier used to represent the attribute in the program. You can specify identifiers in this way for any number of attributes. The default name mapping algorithm is used for the attributes not mentioned.

An object data type may need to be translated for one of two reasons:

- It appears in the INTYPE file.
- It is required to declare another type that must be translated, and the TRANSITIVE parameter is set to TRUE.

If a type that is not mentioned explicitly is required by types declared in exactly one file, then the translation of the required type is written to the same files as the explicitly declared types that require it.

If a type that is not mentioned explicitly is required by types declared in two or more different files, then the translation of the required type is written to the global HFILE file.

---



---

**Note:** You may indicate whether the OTT utility should generate required object types that are not specified in the INTYPE file. Set TRANSITIVE=FALSE so the OTT utility will not to generate required object types. The default is TRANSITIVE=TRUE.

---



---

## Nested #include File Generation

HFILE files generated by the OTT utility #include other necessary files, and #define a symbol constructed from the name of the file. This symbol #defined can then be used to determine if the related HFILE file has already been #included.

Consider, for example, a database with the following types:

```
create type px1 AS OBJECT (col1 number, col2 integer);
create type px2 AS OBJECT (col1 px1);
create type px3 AS OBJECT (col1 px1);
```

The INTYPE file contains the following information:

```
CASE=lower
type px1
    hfile tott95a.h
type px3
    hfile tott95b.h
```

You invoke the OTT utility as follows:

```
>ott hr intype=tott95i.typ outtype=tott95o.typ code=cpp
...
Enter password: password
```

The OTT utility then generates the following two header files, named `tott95a.h` and `tott95b.h`. They are listed in

**Example 8–9 Listing of `ott95a.h`**

```
#ifndef TOTTT95A_ORACLE
# define TOTTT95A_ORACLE

#ifndef OCCI_ORACLE
# include <occi.h>
#endif

/*****
// generated declarations for the PX1 object type.
*****/

class px1 : public oracle::occi::PObject {

protected:
    oracle::occi::Number col1;
    oracle::occi::Number col2;

public:
    void *operator new(size_t size);
    void *operator new(size_t size, const oracle::occi::Connection * sess,
        const OCCI_STD_NAMESPACE::string& table);
    void *operator new(size_t, void *ctxOCCI_);
    void *operator new(size_t size, const oracle::occi::Connection *sess,
        const OCCI_STD_NAMESPACE::string &tableName,
        const OCCI_STD_NAMESPACE::string &typeName,
        const OCCI_STD_NAMESPACE::string &tableSchema,
        const OCCI_STD_NAMESPACE::string &typeSchema);
    void getSQLTypeName(oracle::occi::Environment *env, void **schemaName,
        unsigned int &schemaNameLen, void **typeName,
        unsigned int &typeNameLen) const;
    px1();
    px1(void *ctxOCCI_) : oracle::occi::PObject (ctxOCCI_) { };
    static void *readSQL(void *ctxOCCI_);
    virtual void readSQL(oracle::occi::AnyData& streamOCCI_);
    static void writeSQL(void *objOCCI_, void *ctxOCCI_);
    virtual void writeSQL(oracle::occi::AnyData& streamOCCI_);
    ~px1();
};

#endif
```



**Example 8-10 Listing of ott95b.h**

```

#ifndef TOTTT95B_ORACLE
# define TOTTT95B_ORACLE

#ifndef OCCI_ORACLE
# include <occi.h>
#endif

#ifndef TOTTT95A_ORACLE
# include "tott95a.h"
#endif

/*****
// generated declarations for the PX3 object type.
*****/

class px3 : public oracle::occi::PObject {

protected:
    px1 * coll;

public:
    void *operator new(size_t size);
    void *operator new(size_t size, const oracle::occi::Connection * sess,
        const OCCI_STD_NAMESPACE::string& table);
    void *operator new(size_t, void *ctxOCCI_);
    void *operator new(size_t size, const oracle::occi::Connection *sess,
        const OCCI_STD_NAMESPACE::string &tableName,
        const OCCI_STD_NAMESPACE::string &typeName,
        const OCCI_STD_NAMESPACE::string &tableSchema,
        const OCCI_STD_NAMESPACE::string &typeSchema);
    void getSQLTypeName(oracle::occi::Environment *env, void **schemaName,
        unsigned int &schemaNameLen, void **typeName,
        unsigned int &typeNameLen) const;
    px3();
    px3(void *ctxOCCI_) : oracle::occi::PObject (ctxOCCI_) { };
    static void *readSQL(void *ctxOCCI_);
    virtual void readSQL(oracle::occi::AnyData& streamOCCI_);
    static void writeSQL(void *objOCCI_, void *ctxOCCI_);
    virtual void writeSQL(oracle::occi::AnyData& streamOCCI_);
    ~px3();
};
#endif

```

In the `tott95b.h` file, the symbol `TOTTT95B_ORACLE` is `#define` d at the beginning of the file. This enables you to conditionally `#include` this header file in another file. To accomplish this, you would use the following construct:

```

#ifndef TOTTT95B_ORACLE
#include "tott95b.h"
#endif

```

By using this technique, you can `#include` `tott95b.h` in, say `foo.h`, without having to know whether some other file `#included` in `foo.h` also `#includes` `tott95b.h`.

Next, the file `tott95a.h` is included because it contains the declaration of `struct px1`, that `tott95b.h` requires. When the INTYPE file requests that type declarations be written to more than one file, the OTT utility determines which other files each HFILE must `#include`, and generates each necessary `#include`.

Note that the OTT utility uses quotes in this `#include`. When a program including `tott95b.h` is compiled, the search for `tott95a.h` begins where the source program was found, and will thereafter follow an implementation-defined search rule. If `tott95a.h` cannot be found in this way, then a complete filename (for example, a UNIX absolute path name beginning with a slash character (/)) should be used in the INTYPE file to specify the location of `tott95a.h`.

## OTT Utility Data Type Mappings

When the OTT utility generates a C++ class from a database type, the structure or class contains one element corresponding to each attribute of the object type. The data types of the attributes are mapped to types that are used in Oracle object data types. The data types found in Oracle include a set of predefined, primitive types and provide for the creation of user-defined types, like object types and collections.

The set of predefined types includes standard types that are familiar to most programmers, including number and character types. It also includes large object data types (for example, BLOB or CLOB).

### **Example 8–11 How to Represent Object Attributes Using the OTT Utility**

Oracle also includes a set of predefined types that are used to represent object type attributes in C++ classes. Consider the following object type definition, and its corresponding OTT-generated structure declarations:

```
CREATE TYPE employee AS OBJECT
( name      VARCHAR2(30),
  empno     NUMBER,
  deptno    NUMBER,
  hiredate  DATE,
  salary    NUMBER
);
```

The OTT utility, assuming that the `CASE` parameter is set to `LOWER` and there are no explicit mappings of type or attribute names, produces the following output:

```
#ifndef DATATYPES_ORACLE
# define DATATYPES_ORACLE

#ifndef OCCI_ORACLE
# include <occi.h>
#endif

/*****
// generated declarations for the EMPLOYEE object type.
*****/

class employee : public oracle::occi::PObject {

protected:
    OCCI_STD_NAMESPACE::string NAME;
    oracle::occi::Number EMPNO;
    oracle::occi::Number DEPTNO;
    oracle::occi::Date HIREDATE;
    oracle::occi::Number SALARY;

public:
    void *operator new(size_t size);
    void *operator new(size_t size, const oracle::occi::Connection * sess,
```

```

        const OCCI_STD_NAMESPACE::string& table);
void *operator new(size_t, void *ctxOCCI_);
void *operator new(size_t size, const oracle::occi::Connection *sess,
    const OCCI_STD_NAMESPACE::string &tableName,
    const OCCI_STD_NAMESPACE::string &typeName,
    const OCCI_STD_NAMESPACE::string &tableSchema,
    const OCCI_STD_NAMESPACE::string &typeSchema);
void getSQLTypeName(oracle::occi::Environment *env, void **schemaName,
    unsigned int &schemaNameLen, void **typeName,
    unsigned int &typeNameLen) const;
employee();
employee(void *ctxOCCI_) : oracle::occi::PObject (ctxOCCI_) { };
static void *readSQL(void *ctxOCCI_);
virtual void readSQL(oracle::occi::AnyData& streamOCCI_);
static void writeSQL(void *objOCCI_, void *ctxOCCI_);
virtual void writeSQL(oracle::occi::AnyData& streamOCCI_);
~employee();

};

#endif

```

Table 8–2 lists the mappings from types that can be used as attributes to object data types that are generated by the OTT utility.

**Table 8–2 C++ Object Data Type Mappings for Object Type Attributes**

Object Attribute Types	C++ Mapping
BFILE	Bfile
BLOB	Blob
BINARY_DOUBLE	BDouble
BINARY_FLOAT	BFloat
CHAR (n) , CHARACTER (n)	string
CLOB	Clob
DATE	Date
DEC, DEC (n) , DEC (n,n)	Number
DECIMAL, DECIMAL (n) , DECIMAL (n,n)	Number
FLOAT, FLOAT (n) , DOUBLE PRECISION	Number
INT, INTEGER, SMALLINT	Number
INTERVAL DAY TO SECOND	IntervalDS
INTERVAL YEAR TO MONTH	IntervalYM
Nested Object Type	C++ name of the nested object type
NESTED TABLE	vector<attribute_type>
NUMBER, NUMBER (n) , NUMBER (n,n)	Number
NUMERIC, NUMERIC (n) , NUMERIC (n,n)	Number
RAW	Bytes
REAL	Number
REF	Ref<attribute_type>

**Table 8–2 (Cont.) C++ Object Data Type Mappings for Object Type Attributes**

Object Attribute Types	C++ Mapping
TIMESTAMP, TIMESTAMP WITH TIME ZONE, TIMESTAMP WITH LOCAL TIME ZONE	Timestamp
VARCHAR(n)	string
VARCHAR2(n)	string
VARRAY	vector<attribute_type>

**Example 8–12 How to Map Object Data Types Using the OTT Utility**

The example assumes that the following database types are created:

```
CREATE TYPE my_varray AS VARRAY(5) OF integer;
```

```
CREATE TYPE object_type AS OBJECT
  (object_name VARCHAR2(20));
```

```
CREATE TYPE other_type AS OBJECT
  (object_number NUMBER);
```

```
CREATE TYPE my_table AS TABLE OF object_type;
```

```
CREATE TYPE many_types AS OBJECT
(
  the_varchar   VARCHAR2(30),
  the_char      CHAR(3),
  the_blob      BLOB,
  the_clob      CLOB,
  the_object    object_type,
  another_ref   REF other_type,
  the_ref       REF many_types,
  the_varray    my_varray,
  the_table     my_table,
  the_date      DATE,
  the_num       NUMBER,
  the_raw       RAW(255)
);
```

An INTYPE file should already exist, and include the following:

```
CASE = LOWER
TYPE many_types
```

The following is an example of the OTT type mappings for C++, given the types created in the example in the previous section, and an INTYPE file that includes the following:

```
CASE = LOWER
TYPE many_types

#ifdef MYFILENAME_ORACLE
#define MYFILENAME_ORACLE

#ifdef OCCI_ORACLE
#include <occi.h>
#endif

/*****
```

```

// generated declarations for the OBJECT_TYPE object type.
/*****/

class object_type : public oracle::occi::PObject
{
protected:
    OCCI_STD_NAMESPACE::string object_name;

public:
    void *operator new(size_t size);
    void *operator new(size_t size, const oracle::occi::Connection * sess,
        const OCCI_STD_NAMESPACE::string& table);
    void getSQLTypeName(oracle::occi::Environment *env, void **schemaName,
        unsigned int &schemaNameLen, void **typeName,
        unsigned int &typeNameLen) const;

    object_type();
    object_type(void *ctxOCCI_) : oracle::occi::PObject (ctxOCCI_) { };
    static void *readSQL(void *ctxOCCI_);
    virtual void readSQL(oracle::occi::AnyData& streamOCCI_);
    static void writeSQL(void *objOCCI_, void *ctxOCCI_);
    virtual void writeSQL(oracle::occi::AnyData& streamOCCI_);
};

/*****/
// generated declarations for the OTHER_TYPE object type.
/*****/

class other_type : public oracle::occi::PObject
{
protected:
    oracle::occi::Number object_number;

public:
    void *operator new(size_t size);
    void *operator new(size_t size, const oracle::occi::Connection * sess,
        const OCCI_STD_NAMESPACE::string& table);
    void getSQLTypeName(oracle::occi::Environment *env, void **schemaName,
        unsigned int &schemaNameLen, void **typeName,
        unsigned int &typeNameLen) const;

    other_type();
    other_type(void *ctxOCCI_) : oracle::occi::PObject (ctxOCCI_) { };
    static void *readSQL(void *ctxOCCI_);
    virtual void readSQL(oracle::occi::AnyData& streamOCCI_);
    static void writeSQL(void *objOCCI_, void *ctxOCCI_);
    virtual void writeSQL(oracle::occi::AnyData& streamOCCI_);
};

/*****/
// generated declarations for the MANY_TYPES object type.
/*****/

class many_types : public oracle::occi::PObject
{
protected:
    OCCI_STD_NAMESPACE::string the_varchar;
    OCCI_STD_NAMESPACE::string the_char;
    oracle::occi::Blob the_blob;
    oracle::occi::Clob the_clob;
    object_type * the_object;
    oracle::occi::Ref< other_type > another_ref;
};

```

```

oracle::occi::Ref< many_types > the_ref;
OCCI_STD_NAMESPACE::vector< oracle::occi::Number > the_varray;
OCCI_STD_NAMESPACE::vector< object_type * > the_table;
oracle::occi::Date the_date;
oracle::occi::Number the_num;
oracle::occi::Bytes the_raw;

public:
void *operator new(size_t size);
void *operator new(size_t size, const oracle::occi::Connection * sess,
const OCCI_STD_NAMESPACE::string& table);
void getSQLTypeName(oracle::occi::Environment *env, void **schemaName,
unsigned int &schemaNameLen, void **typeName,
unsigned int &typeNameLen) const;

many_types();
many_types(void *ctxOCCI_) : oracle::occi::PObject (ctxOCCI_) { };
static void *readSQL(void *ctxOCCI_);
virtual void readSQL(oracle::occi::AnyData& streamOCCI_);
static void writeSQL(void *objOCCI_, void *ctxOCCI_);
virtual void writeSQL(oracle::occi::AnyData& streamOCCI_);
};

#endif

```

The OTT utility generates the following C++ class declarations (comments are not part of the OTT output, and are added only to clarify the example):

For C++, when TRANSITIVE=TRUE, the OTT utility automatically translates any types that are used as attributes of a type being translated, including types that are only being accessed by a pointer or REF in an object type attribute. Even though only the `many_types` object was specified in the INTYPE file for the C++ example, a class declaration was generated for all the object types, including the `other_type` object, which was only accessed by a REF in the `many_types` object.

## Default Name Mapping

When the OTT utility creates a C or C++ identifier name for an object type or attribute, it translates the name from the database character set to a legal C or C++ identifier. First, the name is translated from the database character set to the character set used by the OTT utility. Next, if a translation of the resulting name is supplied in the INTYPE file, that translation is used. Otherwise, the OTT utility translates the name character-by-character to the compiler character set, applying the character case specified in the CASE parameter. The following text describes this in more detail.

When the OTT utility reads the name of a database entity, the name is automatically translated from the database character set to the character set used by the OTT utility. In order for the OTT utility to read the name of the database entity successfully, all the characters of the name must be found in the OTT character set, although a character may have different encodings in the two character sets.

The easiest way to guarantee that the character set used by the OTT utility contains all the necessary characters is to make it the same as the database character set. Note, however, that the OTT character set must be a superset of the compiler character set. That is, if the compiler character set is 7-bit ASCII, then the OTT character set must include 7-bit ASCII as a subset, and if the compiler character set is 7-bit EBCDIC, then the OTT character set must include 7-bit EBCDIC as a subset. The user specifies the character set that the OTT utility uses by setting the NLS\_LANG environment variable, or by some other operating system-specific mechanism.

Once the OTT utility has read the name of a database entity, it translates the name from the character set used by the OTT utility to the compiler's character set. If a translation of the name appears in the `INTYPE` file, then the OTT utility uses that translation.

Otherwise, the OTT utility attempts to translate the name as follows:

1. If the OTT character set is a multibyte character set, all multibyte characters in the name that have single-byte equivalents are converted to those single-byte equivalents.
2. The name is converted from the OTT character set to the compiler character set. The compiler character set is a single-byte character set such as `US7ASCII`.
3. The case of letters is set according to how the `CASE` parameter is defined, and any character that is not legal in a C or C++ identifier, or that has no translation in the compiler character set, is replaced by an underscore character (`_`). If at least one character is replaced by an underscore, then the OTT utility gives a warning message. If all the characters in a name are replaced by underscores, the OTT utility gives an error message.

Character-by-character name translation does not alter underscores, digits, or single-byte letters that appear in the compiler character set, so legal C or C++ identifiers are not altered.

Name translation may, for example, translate accented single-byte characters such as `ö` with an umlaut or an `à` with an accent grave to `o` or `a`, with no accent, and may translate a multibyte letter to its single-byte equivalent. Name translation will typically fail if the name contains multibyte characters that lack single-byte equivalents. In this case, the user must specify name translations in the `INTYPE` file.

The OTT utility will not detect a naming clash caused by two or more database identifiers being mapped to the same C name, nor will it detect a naming problem where a database identifier is mapped to a C keyword.

## Overview of the OUTTYPE File

The `OUTTYPE` file is named on the OTT command line. When the OTT utility generates a C++ header file, it also writes the results of the translation into the `OUTTYPE` file. This file contains an entry for each of the translated types, including its version string and the header file to which its C++ representation was written.

The `OUTTYPE` file from one OTT utility run can be used as the `INTYPE` file for a subsequent invocation of the OTT utility.

### **Example 8–13** *OUTTYPE File Generated by the OTT Utility*

In this `INTYPE` file, the programmer specifies the case for OTT-generated C++ identifiers, and provides a list of types that should be translated. In two of these types, naming conventions are specified. This is what the `OUTTYPE` file looks like after running the OTT utility:

The following example shows what t:

```
CASE = LOWER
TYPE EMPLOYEE AS employee
    VERSION = "$8.0"
    HFILE = demo.h
    TRANSLATE SALARY$ AS salary
                DEPTNO AS department
TYPE ADDRESS AS ADDRESS
```

```
VERSION = "$8.0"  
HFILE = demo.h  
TYPE ITEM AS item  
VERSION = "$8.0"  
HFILE = demo.h  
TYPE "Person" AS Person  
VERSION = "$8.0"  
HFILE = demo.h  
TYPE PURCHASE_ORDER AS p_o  
VERSION = "$8.0"  
HFILE = demo.h
```

When examining the contents of the OUTTYPE file, you might discover types listed that were not included in the INTYPE file specification. For example, consider the case where the INTYPE file only specified that the `person` type was to be translated:

```
CASE = LOWER  
TYPE PERSON
```

If the definition of the `person` type includes an attribute of type `address`, then the OUTTYPE file includes entries for both `PERSON` and `ADDRESS`. The `person` type cannot be translated completely without first translating `address`.

The OTT utility analyzes the types in the INTYPE file for type dependencies before performing the translation, and translates other types as necessary.

---

---

**Note:** To specify that the OTT utility should not generate required object types that are not specified in the INTYPE file, set `TRANSITIVE=FALSE`. The default is `TRANSITIVE=TRUE`.

---

---


## The OTT Utility and OCCI Applications

The OTT utility generates objects and maps SQL data types to C++ classes. The OTT utility also implements a few methods called by OCCI when instantiating objects and a function that is called in the OCCI application to register the mappings with the environment. These declarations are stored in a header file that you include (`#include`) in your OCCI application. The prototype for the function that registers the mappings is written to a separate header file that you also include in your OCCI application. The method implementations are stored in a C++ source code file (with extension `.cpp`) that is linked with the OCCI application. The function that registers the mappings is stored in a separate C++ (`xxx.cpp`) file that is also linked with the application.

[Figure 8–1](#) shows the steps involved in using the OTT utility with OCCI. These steps are described following the figure.



Figure 8-1 The OTT Utility with OCCI



1. Create the type definitions in the database by using the SQL DDL.
2. Create the INTYPE file that contains the database types to be translated by the OTT utility.
3. Specify that C++ should be generated and invoke the OTT utility.

The OTT utility then generates the following files:

- A header file (with the extension `.h`) that contains C++ class representations of object types. The filename is specified on the OTT command line by the `HFILE` parameter.
  - A header file containing the prototype of the function (`MAPFUNC`) that registers the mappings.
  - A C++ source file (with the extension `.cpp`) that contains the static methods to be called by OCCI while instantiating the objects. Do not call these methods directly from your OCCI application. The filename is specified on the OTT command line by the `CPPFILE` parameter.
  - A file that contains the function used to register the mappings with the environment (with the extension `.cpp`). The filename is specified on the OTT command line by the `MAPFILE` parameter.
  - A file (the `OUTTYPE` file) that contains an entry for each of the translated types, including the version string and the file into which it is written. The filename is specified on the OTT command line by the `OUTTYPE` parameter.
4. Write the OCCI application and include the header files created by the OTT utility in the OCCI source code file.

The application declares an environment and calls the function `MAPFUNC` to register the mappings.

5. Compile the OCCI application to create the OCCI object code, and link the object code with the OCCI libraries to create the program executable.

## C++ Classes Generated by the OTT Utility

When the OTT utility generates a C++ class from a database object type, the class declaration contains one element corresponding to each attribute of the object type. The data types of the attribute are mapped to types that are used in Oracle object data types, as defined in [Table 8-2](#) on page 8-19.

For each class, two new operators, `readSQL()` and `writeSQL()` methods are generated. They are used by OCCI to marshal and unmarshal objects.

By default, the C++ classes generated by the OTT utility for an object type are derived from the `PObject` class, so the generated constructor in the class also derives from the `PObject` class. For inherited database types, the class is derived from the parent type class as is the generated constructor and only the elements corresponding to attributes not already in the parent class are included.

Class declarations that include the elements corresponding to the database type attributes and the method declarations are included in the header file generated by the OTT utility. The method implementations are included in the `CPPFILE` file generated by the OTT utility.

### **Example 8-14 How to Generate C++ Classes Using the OTT Utility**

This example demonstrates how to generate C++ classes using the OTT utility:

1. Define the types:

```
CREATE TYPE FULL_NAME AS OBJECT (first_name CHAR(20),
    last_name CHAR(20));
CREATE TYPE ADDRESS AS OBJECT (state CHAR(20), zip CHAR(20));
CREATE TYPE ADDRESS_TAB AS VARRAY(3) OF REF ADDRESS;
CREATE TYPE PERSON AS OBJECT (id NUMBER, name FULL_NAME,
    curr_addr REF ADDRESS, prev_addr_l ADDRESS_TAB) NOT FINAL;
CREATE TYPE STUDENT UNDER PERSON (school_name CHAR(20));
```

2. Provide an `INTYPE` file:

```
CASE = SAME
MAPFILE = RegisterMappings_3.cpp
TYPE FULL_NAME AS FullName
    TRANSLATE first_name as FirstName
            last_name as LastName
TYPE ADDRESS
TYPE PERSON
TYPE STUDENT
```

3. Invoke the OTT utility:

```
ott userid=demoursr intype=demoin_3.typ outtype=demoout_3.typ
code=cpp hfile=demo_3.h cppfile=demo_3.cpp
```

## Map Registry Function

One function to register the mappings with the environment is generated by the OTT utility. The function contains the mappings for all the types translated by the invocation of the OTT utility. The function name is either specified in the `MAPFUNC` parameter or, if that parameter is not specified, derived from `MAPFILE` parameter. The only argument to the function is the pointer to `Environment`.

The function uses the provided `Environment` to get `Map` and then registers the mapping of each translated type.

## Extending C++ Classes

To enhance the functionality of a class generated by the OTT utility, you can derive new classes. You can also add methods to a class, but Oracle does not recommend doing so due to an inherent risk.

**See Also:** ["Carrying Forward User Added Code"](#) on page 8-27 for details on how to use OTT markers to retain code you want to add in OTT generated files

Assume that you want to generate the both `CAddress` and `MyAddress` classes from the SQL object type `ADDRESS`. `MyAddress` class can be derived from `CAddress` class. To do this, the OTT utility must alter the code it generates:

- By using the `MyAddress` class instead of the `CAddress` class to represent attributes whose database type is `ADDRESS`
- By using the `MyAddress` class instead of the `CAddress` class to represent vector and `REF` elements whose database type is `ADDRESS`
- By using the `MyAddress` class instead of the `CAddress` class as the base class for database object types that are inherited from `ADDRESS`. Even though a derived class is a subtype of `MyAddress`, the `readSQL()` and `writeSQL()` methods called are those of the `CAddress` class.

---

**Caution:** When a class is both extended and used as a base class for another generated class, the *inheriting* type class and the *inherited* type class must be generated in separate files.

---

### Example 8–15 How to Extend C++ Classes Using the OTT Utility

To use the OTT utility to generate the `CAddress` class, which is derived from `MyAddress` class), the following clause must be specified in the `TYPE` statement:

```
TYPE ADDRESS GENERATE CAdress AS MyAddress
```

Given the database types `FULL_NAME`, `ADDRESS`, `PERSON`, and `PFGRFDENT` as they were created before and changing the `INTYPE` file to include the `GENERATE . . . AS` clause:

```
CASE = SAME
MAPFILE = RegisterMappings_5.cpp

TYPE FULL_NAME GENERATE CFullName AS MyFullName
  TRANSLATE first_name as FirstName
            last_name as LastName

TYPE ADDRESS GENERATE CAddress AS MyAddress
TYPE PERSON GENERATE CPerson AS MyPerson
TYPE STUDENT GENERATE CStudent AS MyStudent
```

## Carrying Forward User Added Code

To extend the functionality of OTT generated code, at times programmers may want to add code in the OTT generated file. The way OTT can distinguish between OTT

generated code and code added by the user is by looking for some predefined markers (tags). OTT recognizes `OTT_USERCODE_START` as the "start of user code marker", and `OTT_USERCODE_END` as the "end of user code marker".

For OTT marker support, a user block is defined as

```
OTT_USERCODE_START + user added code + OTT_USERCODE_END
```

OTT marker support enables carrying forward the user added blocks in \*.h and \*.cpp files.

## Properties of OTT Markers

These items describe the properties of OTT Markers Support:

1. User must use the command line option `USE_MARKER=TRUE` from the very first time OTT is invoked to generate a file.
2. User should treat markers like other C++ statements; a marker will be defined by OTT in the generated file as follows when the command line option `USE_MARKER=TRUE` is used:

```
#ifndef OTT_USERCODE_START
#define OTT_USERCODE_START
#endif
#ifndef OTT_USERCODE_END
#define OTT_USERCODE_END
#endif
```

3. The markers, `OTT_USERCODE_START` and `OTT_USERCODE_END`, must be preceded and followed by white space.
4. OTT will copy the text/code given within markers verbatim along with the markers while generating the code next time,

User modified code:

```
1 // --- modified generated code
2 OTT_USERCODE_START
3 // --- including "myfullname.h"
4 #ifndef MYFULLNAME_ORACLE
5 #include "myfullname.h"
6 #endif
7 OTT_USERCODE_END
8 // --- end of code addition
```

Carried forward code:

```
1 OTT_USERCODE_START
2 // --- including "myfullname.h"
3 #ifndef MYFULLNAME_ORACLE
4 #include "myfullname.h"
5 #endif
6 OTT_USERCODE_END
```

5. OTT will not be able to carry forward user added code properly if the database `TYPE` or `INTYPE` file undergoes changes as shown in the following cases:
  - If user modifies the case of the type name, OTT will fail to find out the class name with which the code was associated earlier as the case of the class name got modified by the user in the `INTYPE` file.

**CASE=UPPER**

**CASE=LOWER**

```

TYPE employee
TRANSLATE SALARY$ AS salary
    DEPTNO AS department
TYPE ADDRESS
TYPE item
TYPE "Person"
TYPE PURCHASE_ORDER AS p_o

```

```

TYPE employee
TRANSLATE SALARY$ AS salary
    DEPTNO AS department
TYPE ADDRESS
TYPE item
TYPE "Person"
TYPE PURCHASE_ORDER AS p_o

```

- If user asks to generate the class with different name (GENERATE AS clause of INTYPE file), OTT will fail to find out the class name with which the code was associated earlier as the class name got modified by the user in the INTYPE file.

```

CASE=LOWER
TYPE employee
TRANSLATE SALARY$ AS salary
    DEPTNO AS department
TYPE ADDRESS
TYPE item
TYPE "Person"
TYPE PURCHASE_ORDER AS p_o

```

```

CASE=LOWER
TYPE employee
TRANSLATE SALARY$ AS salary
    DEPTNO AS department
TYPE ADDRESS
TYPE item
TYPE "Person"
TYPE PURCHASE_ORDER AS
purchase_order

```

6. If OTT encounters an error while parsing an .h or .cpp file, it reports the error and leaves the file having error as it is so that the user can go back and correct the error reported, and rerun OTT.
7. OTT will flag an error if:
  - it does not find a matching OTT\_USERCODE\_END for OTT\_USERCODE\_START encountered
  - markers are nested (OTT finds next OTT\_USERCODE\_START before OTT\_USERCODE\_END is found for the previous OTT\_USERCODE\_START)
  - OTT\_USERCODE\_END is encountered before OTT\_USERCODE\_START

## Using OTT Markers

The user must use command line option USE\_MARKER=TRUE to turn on marker support. There are two general ways in which OTT markers can carry forward user added code:

1. **User code added in .h file.**
  - **User code added in global scope.** This is typically the case when user needs to include different header files, forward declaration, and so on. Refer to the code example provided later.
  - **User code added in class declaration.** At any point of time OTT generated class declaration will have private scope for data members and public scope for methods, or protected scope for data members and public scope for methods. User blocks can be added after all OTT generated declarations in either access specifiers.

### **Example 8–16 How to Add User Code to a Header File Using OTT Utility**

```

...
#ifdef OTT_USERCODE_START
#define OTT_USERCODE_START
#endif
#ifdef OTT_USERCODE_END

```

```

#define OTT_USERCODE_END
#endif

#ifndef OCCI_ORACLE
#include <occi.h>
#endif

OTT_USERCODE_START    // user added code
...
OTT_USERCODE_END

#ifndef ...            // OTT generated include
#include " ... "
#endif

OTT_USERCODE_START    // user added code
...
OTT_USERCODE_END

class <class_name_1> : public oracle::occi::PObject
{ protected:
    ...                // OTT generated data members
    OTT_USERCODE_START // user added code for data member / method
    ...                // declaration / inline method
    OTT_USERCODE_END

public:
    void *operator new(size_t size);
    ...
    OTT_USERCODE_START // user added code for data member / method
    ...                // declaration / inline method definition
    OTT_USERCODE_END
};

OTT_USERCODE_START    // user added code
...
OTT_USERCODE_END

class <class_name_2> : public oracle::occi::PObject
{
    ...
};

OTT_USERCODE_START    // user added code
...
OTT_USERCODE_END
...
#endif                // end of .h file

```

2. **User code added in .cpp file.** OTT will support adding a new user defined method within OTT markers. The user block must be added at the beginning of the file, just after the includes and before the definition of OTT generated methods. If there are more than one OTT generated includes, user code can also be added between OTT generated includes. User code added in any other part of a `xxx.cpp` file will not be carried forward.

**Example 8–17 How to Add User Code to the Source File Using the OTT Utility**

```

#ifndef OTT_USERCODE_START
#define OTT_USERCODE_START

```

```
#endif

#ifdef OTT_USERCODE_END
#define OTT_USERCODE_END
#endif
...
    OTT_USERCODE_START    // user added code
    ...
    OTT_USERCODE_END
...
    OTT_USERCODE_START    // user added code
    ...
    OTT_USERCODE_END

/*****
/ generated method implementations for the ... object type.
*****/

void *<class_name_1>::operator new(size_t size)
{
    return oracle::occi::PObject::operator new(size);
}
...
// end of .cpp file
```





---

---

# Globalization and Unicode Support

This chapter describes OCCI support for multibyte and Unicode charactersets.

This chapter contains these topics:

- [Overview of Globalization and Unicode Support](#)
- [Specifying Charactersets](#)
- [Data Types for Globalization and Unicode Support](#)
- [Objects and OTT Support](#)

## Overview of Globalization and Unicode Support

OCCI now enables application development in all Oracle supported multibyte and Unicode charactersets. The UTF16 encoding of Unicode is fully supported. Application programs can specify their charactersets when the OCCI Environment is created. OCCI interfaces that take character string arguments (such as SQL statements, username, s, error messages, object names, and so on) have been extended to handle data in any character set. Character data from relational tables or objects can be in any character set. OCCI can be used to develop multi-lingual, global and Unicode applications.

## Specifying Charactersets

OCCI applications need to specify the client character set and client national character set when initializing the OCCI Environment. The client character set specifies the character set for all SQL statements, object/user names, error messages, and data of all CHAR data type (CHAR, VARCHAR2, LONG) columns/attributes. The client national character set specifies the character set for data of all NCHAR data type (NCHAR, NVARCHAR2) columns/attributes.

A new `createEnvironment()` interface that takes the client character set and client national character set is now provided. This allows OCCI applications to set character set information dynamically, independent of the `NLS_LANG` and `NLS_CHAR` initialization parameter.

### **Example 9–1 How to Use Globalization and Unicode Support**

```
Environment *env = Environment:createEnvironment("JA16SJIS", "UTF8");
```

This statement creates a OCCI Environment with JA16SJIS as the client character set and UTF8 as the client national character set.

Any valid Oracle character set name (except 'AL16UTF16') can be passed to `createEnvironment()`. A OCCI specific string "OCCIUTF16" (in uppercase) can be passed to specify UTF16 as the character set.

```
Environment *env = Environment::createEnvironment("OCCIUTF16", "OCCIUTF16");
Environment *env = Environment::createEnvironment("US7ASCII", "OCCIUTF16");
```

---

---

**Note:** If an application specifies "OCCIUTF16" as the client character set (first argument), then the application should use only the UTF16 interfaces of OCCI. These interfaces take `UString` argument types

The character sets in the OCCI Environment are client-side only. They indicate the character sets the OCCI application uses to interact with Oracle. The database character set and database national character set are specified when the database is created. Oracle converts all data from the client character set/national character set to the database character set/national character set before the server processes the data.

---

---

## Data Types for Globalization and Unicode Support

The data types used for supporting globalization and use of unicode include [UString Data Type](#), [Multibyte and UTF16 data](#), and [CLOB and NCLOB Data Types](#).

### UString Data Type

`UString` is a data type that enables applications and the OCCI library to pass and receive Unicode data in UTF-16 encoding. `UString` is templated from the C++ STL `basic_string` with Oracle's `utext` data type.

```
typedef basic_string<utext> UString;
```

Oracle's `utext` data type is a 2 byte short data type and represents Unicode characters in the UTF-16 encoding. A Unicode character's codepoint can be represented in 1 `utext` or 2 `utexts` (2 or 4 bytes). Characters from European and most Asian scripts are represented in a single `utext`. Supplementary characters defined in the Unicode 3.1 standard are represented with 2 `utext` elements.

In Microsoft Windows platforms, `UString` is equivalent to the C++ standard `wstring` data type. This is because the `wchar_t` data type is type defined to a 2 byte short in these platforms, which is same as Oracle's `utext`, allowing applications to use a `wstring` type variable where a `UString` would be normally required. Consequently, applications can also pass wide-character string literals, created by prefixing the literal with the letter 'L', to OCCI Unicode APIs.

#### **Example 9-2 Using `wstring` Data Type**

```
//bind Unicode data using wstring data type
//binding the Euro symbol, UTF16 codepoint 0x20AC
wchar_t eurochars[] = {0x20AC,0x00};
wstring eurostr(eurochars);
stmt->setUString(1,eurostr);

//Call the Unicode version of createConnection by
//passing widechar literals
Connection *conn = env->createConnection(L"HR",L"password",L"");
```

OCCI applications should use the `UString` data type for data in UTF16 character set

## Multibyte and UTF16 data

For data in multibyte character sets like JA16SJIS and UTF8, applications should use the C++ `string` type. The existing OCCI APIs that take `string` arguments can handle data in any multibyte character set. Due to the use of `string` type, OCCI supports only byte length semantics for multibyte character set strings.

### Example 9-3 Binding UTF8 Data Using the `string` Data Type

```
//bind UTF8 data
//binding the Euro symbol, UTF8 codepoint : 0xE282AC
char eurochars[] = {0xE2,0x82,0xAC,0x00};
string eurostr(eurochars)
stmt->setString(1,eurostr);//use the string interface
```

For Unicode data in the UTF16 character set, the OCCI specific data type: `UString` and the OCCI UTF16 interfaces should be used.

### Example 9-4 Binding UTF16 Data Using the `UString` Data Type

```
//bind Unicode data using UString data type
//binding the Euro symbol, UTF16 codepoint 0x20AC
utext eurochars[] = {0x20AC,0x00};
UString eurostr(eurochars);
stmt->setUString(1,eurostr);//use the UString interface
```

## CLOB and NCLOB Data Types

Oracle provides the `CLOB` and `NCLOB` data types for storing and processing large amounts of character data. `CLOBs` represent data in the database character set and `NCLOBs` represent data in the database national character set. `CLOBs` and `NCLOBs` can be used as column types in relational tables and as attributes in object types.

The OCCI `Clob` class is used to work with both `CLOB` and `NCLOB` data types. If the database type is `NCLOB`, then the `Clob` `setCharSetForm()` method should be called with `OCCI_SQLCS_NCHAR` before reading/writing from the `LOB`.

The OCCI `Clob` class has support for multibyte and UTF16 character sets. By default, the `Clob` interfaces assume the data is encoded in the client-side character set (for both `CLOBs` and `NCLOBs`). To specify a different character set or to specify the client-side national character set for a `NCLOB`, call the `setCharSetId()` or `setCharSetIdUString()` methods with the appropriate character set. The OCCI specific string `'OCCIUTF16'` can be passed to indicate UTF16 as the character set.

### Example 9-5 Using `CLOB` and `NCLOB` Data Types

```
//client character set - ZHT16BIG5, national character set - UTF16
Environment *env = Environment::createEnvironment("ZHT16BIG5","OCCIUTF16");
...
Clob nclobvar;
//for NCLOBs, need to call setCharSetForm method.
nclobvar.setCharSetForm(OCCI_SQLCS_NCHAR);
...
//if reading/writing data in UTF16 for this NCLOB, still need to
//explicitly call setCharSetId
nclobvar.setCharSetId("OCCIUTF16")
```

To read or write data in multibyte character sets, use the existing read and write interfaces that take a char buffer. New overloaded interfaces that take utext buffers for UTF16 data have been added to the [Clob Class](#) as `read()`, `write()` and `writeChunk()` methods. The arguments and return values for these methods are either bytes or characters, depending on the character set of the LOB.

## Objects and OTT Support

Multibyte and UTF16 character sets are supported for handling character data in object attributes. All CHAR data type (CHAR/VARCHAR2) attributes hold data in the client-side character set, while all NCHAR data type (NCHAR/NVARCHAR2) attributes hold data in the client-side national character set. A member variable of UString data type represents an attribute in UTF16 character set.

### See Also:

- [Chapter 13, "OCI Application Programming Interface"](#): two new versions of `operator new()` on page 13-164 that have been added to the [PObject Class](#) for object support
- [Chapter 8, "Object Type Translator Utility"](#): a new `UNICODE` parameter on page 8-9 that has been added for OTT utility support.

---

---

## Oracle Streams Advanced Queuing

This chapter describes the OCCI implementation of Oracle Streams Advanced Queuing (AQ) for messages.

This chapter contains these topics:

- [Overview of Oracle Streams Advanced Queuing](#)
- [AQ Implementation in OCCI](#)
- [Creating Messages](#)
- [Enqueuing Messages](#)
- [Dequeuing Messages](#)
- [Listening for Messages](#)
- [Registering for Notification](#)
- [Message Format Transformation](#)

**See Also:**

- *Oracle Streams Advanced Queuing User's Guide* for basic concepts of Advanced Queuing
- [Chapter 13, "OCCI Application Programming Interface"](#)

### Overview of Oracle Streams Advanced Queuing

Oracle Streams is a new information sharing feature that provides replication, message queuing, data warehouse loading, and event notification. It is also the foundation behind Oracle Streams Advanced Queuing (AQ).

Advanced Queuing is the integrated message queuing feature that exposes message queuing capabilities of Oracle Streams. AQ enables applications to:

- Perform message queuing operations similar to SQL operations from the Oracle database
- Communicate asynchronously through messages in AQ queues
- Integrate with database for unprecedented levels of operational simplicity, reliability, and security to message queuing
- Audit and track messages
- Supports both synchronous and asynchronous modes of communication

**See Also:**

<http://www.oracle.com/technology/products/dataint/>  
for more information about the Advanced Queuing feature

The advantages of using AQ in OCCI applications include:

- Create applications that communicate with each other in a consistent, reliable, secure, and autonomous manner
- Store messages in database tables, bringing the reliability and recoverability of the database to your messaging infrastructure
- Retain messages in the database automatically for auditing and business intelligence
- Create applications that leverage messaging without having to deal with a different security, data type, or operational mode
- Leverage transactional characteristics of the database

Since traditional messaging solutions have single subscriber queues, a queue must be created for each pair of applications that communicate with each other. The publish/subscribe protocol of the AQ makes it easy to add additional applications (subscribers) to a conversation between multiple applications.

## AQ Implementation in OCCI

OCCI AQ is a set of interfaces that allows messaging clients to access the Advanced Queuing feature of Oracle for enterprise messaging applications. Currently, OCCI AQ supports only the operational interfaces and not the administrative interface, but administrative operations can be accessed through embedded PL/SQL calls.

**See Also:** Package `DBMS_AQADM` in *Oracle Database PL/SQL Packages and Types Reference* for administrative operations in AQ support through PL/SQL

The AQ feature can be used in conjunction with other interfaces available through OCCI for sending, receiving, publishing, and subscribing in a message-enabled database. Synchronous and asynchronous message consumption is available based on a message selection rule.

Enqueuing refers to sending a message to a queue and dequeuing refers to receiving one. A client application can create a message, set the desired properties on it and enqueue it by storing the message in the queue, a table in the database. When dequeuing a message, an application can either dequeue it synchronously by calling receive methods on the queue, or asynchronously by waiting for a notification from the database.

The AQ feature is implemented through the abstractions [Message](#), [Agent](#), [Producer](#), [Consumer](#), [Listener](#) and [Subscription](#).

### Message

A message is the basic unit of information being inserted into and retrieved from a queue. A message consists of control information and payload data. The control information represents message properties used by AQ to manage messages. The payload data is the information stored in the queue and is transparent to AQ.

**See Also:** [Message Class](#) documentation in [Chapter 13, "OCCI Application Programming Interface"](#)

## Agent

An `Agent` represents and identifies a user of the queue, either producer or consumer of the message, either an end-user or an application. An `Agent` is identified by a name, an address and a protocol. The name can be either assigned by the application, or be the application itself. The address is determined in terms of the communication protocol. If the protocol is 0 (default), the address is of the form `[schema.]queueName[@dblink]`, a database link.

Agents on the same queue must have a unique combination of name, address, and protocol. [Example 10–1](#) demonstrates an instantiation of a new `Agent` object in a client program.

### **Example 10–1** *Creating an Agent*

```
Agent agt(env, "Billing_app", "billqueue", 0);
```

**See Also:** [Agent Class](#) documentation in [Chapter 13, "OCCI Application Programming Interface"](#)

## Producer

A client uses a `Producer` object to enqueue Messages into a queue. It is also used to specify various enqueue options.

**See Also:** [Producer Class](#) documentation in [Chapter 13, "OCCI Application Programming Interface"](#)

## Consumer

A client uses a `Consumer` object to dequeue Messages that have been delivered to a queue. It also specifies various dequeuing options.

Before a consumer can receive messages,

### **Example 10–2** *Setting the Agent on the Consumer*

```
Consumer cons(conn);
...
cons.setAgent(ag);
cons.receive();
```

**See Also:** [Consumer Class](#) documentation in [Chapter 13, "OCCI Application Programming Interface"](#)

## Listener

A `Listener` listens for Messages for registered Agents at specified queues.

**See Also:** [Listener Class](#) documentation in [Chapter 13, "OCCI Application Programming Interface"](#)

## Subscription

A `Subscription` encapsulates the information and operations necessary for registering a subscriber for notifications.

## Creating Messages

As mentioned previously, a `Message` is a basic unit of information that contains both the properties of the message and its content, or **payload**. Each message is enqueued by the `Producer` and dequeued by the `Consumer` objects.

## Message Payloads

OCCI supports three types of message payloads: [RAW](#), [AnyData](#), and [User-defined](#).

### RAW

RAW payloads are mapped as objects of the [Bytes Class](#) in OCCI.

### AnyData

The `AnyData` type models self-descriptive data encapsulation; it contains both the type information and the actual data value. Data values of most SQL types can be converted to `AnyData`, and then be converted to the original data type. `AnyData` also supports user-defined data types. The advantage of using `AnyData` payloads is that it ensures both type preservation after an enqueue and dequeue process, and that it allows the user to use a single queue for all types used in the application.

[Example 10-3](#) demonstrates how to create an `AnyData` message. [Example 10-4](#) shows how to retrieve the original data type from the message.

#### **Example 10-3** *Creating an AnyData Message with a String Payload*

```
AnyData any(conn);
any.setFromString("item1");
Message mes(env);
mes.setAnyData(any);
```

#### **Example 10-4** *Determining the Type of the Payload in an AnyData Message*

```
TypeCode tc = any.getType();
```

### User-defined

OCCI supports enqueueing and dequeueing of user-defined types as payloads.

[Example 10-5](#) demonstrates how to create a payload with a user-defined `Employee` object.

#### **Example 10-5** *Creating a User-defined Payload*

```
// Assuming type Employee ( name varchar2(25),
//                               deptid number(10),
//                               manager varchar2(25) )
Employee *emp = new Employee();
emp.setName("Scott");
emp.setDeptid(10);
emp.setManager("James");
Message mes(env);
mes.setObject(emp);
```



## Message Properties

Aside from payloads, the user can specify several additional message properties, such as [Correlation](#), [Sender](#), [Delay and Expiration](#), [Recipients](#), and [Priority and Ordering](#).

### Correlation

Applications can specify a correlation identifier of the message during the enqueueing process, as demonstrated in [Example 10–6](#). This identifier can then be used by the dequeuing application.

#### **Example 10–6 Specifying the Correlation identifier**

```
mes.setCorrelationId("enq_corr_di");
```

### Sender

Applications can specify the sender of the message, as demonstrated in [Example 10–7](#). The sender identifier can then be used by the receiver of the message.

#### **Example 10–7 Specifying the Sender identifier**

```
mes.setSenderId(agt);
```

### Delay and Expiration

Time settings control the delay and expiration times of the message in seconds, as demonstrated in [Example 10–8](#).

#### **Example 10–8 Specifying the Delay and Expiration times of the message**

```
mes.setDelay(10);
mes.setExpirationTime(60);
```

### Recipients

The agents for whom the message is intended can be specified during message encoding, as demonstrated in [Example 10–9](#). This ensures that only the specified recipients can access the message.

#### **Example 10–9 Specifying message recipients**

```
vector<Agent> agt_list;
for (i=0; i<num_recipients; i++)
    agt_list.push_back(Agent(name, address, protocol));
mes.setRecipientList(agt_list);
```

### Priority and Ordering

By assigning a priority level to a message, the sender can control the order in which the messages are dequeued by the receiver. [Example 10–10](#) demonstrates how to set the priority of a message.

#### **Example 10–10 Specifying the Priority of a Message**

```
mes.setPriority(3);
```

## Enqueuing Messages

Messages are enqueued by the `Producer`. The [Producer Class](#) is also used to specify enqueue options. A `Producer` object can be created on a valid connection where enqueueing will be performed, as illustrated in [Example 10–11](#).

The transactional behavior of the enqueue operation can be defined based on application requirements. The application can make the effect of the enqueue operation visible externally either immediately after it is completed, as in [Example 10–11](#), or only after the enclosing transaction has been committed.

To enqueue the message, use the `send()` method, as demonstrated in [Example 10–11](#). A client may retain the `Message` object after it is sent, modify it, and send it again.

### **Example 10–11** *Creating a Producer, Setting Visibility, and Enqueuing the Message*

```
Producer prod(conn);
...
prod.setVisibility(Producer::ENQ_IMMEDIATE);
...
Message mes(env);
...
mes.setBytes(obj);           // obj represents the content of the message
prod.send(mes, queueName);  // queueName is the name of the queue
```

## Dequeuing Messages

Messages delivered to a queue are dequeued by the `Consumer`. The [Consumer Class](#) is also used to specify dequeue options. A `Consumer` object can be created on a valid connection to the database where a queue exists, as demonstrated in [Example 10–12](#).

In applications that support multiple consumers in the same queue, the name of the consumer has to be specified as a registered subscriber to the queue, as shown in [Example 10–12](#).

To dequeue the message, use the `receive()` method, as demonstrated in [Example 10–12](#). The `typeName` and `schemaName` parameters of the `receive()` method specify the type of payload and the schema of the payload type.

### **Example 10–12** *Creating a Consumer, Naming the Consumer, and Receiving a Message*

```
Consumer cons(conn);
...
// Name must be registered with the queue through administrative interface
cons.setConsumerName("BillApp");
cons.setQueueName(queueName);
...
Message mes = cons.receive(Message::OBJECT, "BILL_TYPE", "BILL_PROCESSOR");
...
// obj is assigned the content of the message
obj = mes.getObject();
```

When the queue payload type is either `RAW` or `AnyData`, `schemaName` and `typeName` are optional, but you must specify these parameters explicitly when working with user-defined payloads. This is illustrated in [Example 10–13](#).

### **Example 10–13** *Receiving a Message*

```
//receiving a RAW message
```

```

Message mes = cons.receive(Message::RAW);
...
//receiving an ANYDATA message
Message mes = cons.receive(Message::ANYDATA);
...

```

## Dequeuing Options

The dequeuing application can specify several dequeuing options before it begins to receive messages. These include [Correlation](#), [Mode](#), and [Navigation](#).

### Correlation

The message can be dequeued based on the value of its correlation identifier using the `setCorrelationId()` method, as shown in [Example 10–14](#).

### Mode

Based on application requirements, the user can choose to only browse through messages in the queue, remove the messages from the queue, or lock messages using the `setDequeueMode()` method, as shown in [Example 10–14](#).

### Navigation

Messages enqueued in a single transaction can be viewed as a single group by implementing the `setPositionOfMessage()` method, as shown in [Example 10–14](#).

#### **Example 10–14** *Specifying dequeuing options*

```

cons.setCorrelationId(corrId);
...
cons.setDequeueMode(deqMode);
...
cons.setPositionOfMessage(Consumer::DEQ_NEXT_TRANSACTION);

```

## Listening for Messages

The Listener listens for messages on queues on behalf of its registered clients. The [Listener Class](#) implements the `listen()` method, which is a blocking call that returns once a queue has a message for one of the registered agents, or throws an error when the time out period expires. [Example 10–15](#) illustrates the listening protocol.

#### **Example 10–15** *Listening for messages*

```

Listener listener(conn);

vector<Agent> agtList;
for( int i=0; i<num_agents; i++)
    agtList.push_back( Agent( name, address, protocol);

listener.setAgentList(agtList);
listener.setTimeoutForListen(10);

Agent agt(env);

try{
    agt = listener.listen();
}

```

```
catch{
    cout<<e.getMessage()<<endl;
}
```

## Registering for Notification

The [Subscription Class](#) implements the publish-subscribe notification feature. It allows an OCCI AQ application to receive client notifications directly, register an e-mail address to which notifications can be sent, register an HTTP URL to which notifications can be posted, or register a PL/SQL procedure to be invoked on a notification. Registered clients are notified asynchronously when events are triggered or on an explicit AQ enqueue. Clients do not need to be connected to a database.

An OCCI application can do all of the following:

- Register interest in notification in the AQ namespace, and be notified when an enqueue occurs.
- Register interest in subscriptions to database events, and receive notifications when these events are triggered.
- Manage registrations, such as disable registrations temporarily, or dropping registrations entirely.
- Post (or send) notifications to registered clients.

## Publish-Subscribe Notifications

Notifications can work in several ways. They can be:

- received directly by the OCCI application
- sent to a pre-specified e-mail address
- sent to a pre-defined HTTP URL
- invoke a pre-specified database PL/SQL procedure

Registered clients are notified asynchronously when events are triggered, or on an explicit AQ enqueue. Clients do not need to be connected to a database for notifications to work. Registration can be accomplished either as [Direct Registration](#) or [Open Registration](#).

### Direct Registration

You can register directly with the database. This is relatively simple, and the registration takes effect immediately. [Example 10–16](#) outlines the required steps to successfully register for direct event notification. It is assumed that the appropriate event trigger or queue is in existence, and that the initialization parameter `COMPATIBLE` is set to 8.1 or higher.

#### **Example 10–16 How to Register for Notifications; Direct Registration**

1. Create the environment in `Environment::EVENTS` mode.
2. Create the `Subscription` object.
3. Set these `Subscription` attributes.

The namespace can be set to these options:

- To receive notifications from AQ queues, `namespace` must be set to `Subscription::NS_AQ`. The subscription name is then either of the form

`SCHEMA.QUEUE` when registering on a single consumer queue, or `SCHEMA.QUEUE:CONSUMER_NAME` when registering on a multi-consumer queue.

- To receive notifications from other applications that use `conn->postToSubscription()` method, namespace must be set to `Subscription::NS_ANONYMOUS`

The protocol can be set to these options:

- If an OCCI client needs to receive an event notification, this attribute should be set to `Subscription::PROTO_CBK`. You also need to set the notification callback and the subscription context before registering the `Subscription`. The notification callback will be called when the event occurs.
- For an e-mail notification, set the protocol to `Subscription::PROTO_MAIL`. You must set the recipient name prior to subscribing to avoid an application error.
- For an HTTP URL notification, set the protocol to `Subscription::HTTP`. You must set the recipient name prior to subscribing to avoid an application error.
- To invoke PL/SQL procedures in the database on event notification, set protocol to `Subscription::PROTO_SERVER`. You must set the recipient name prior to subscribing to avoid an application error.

4. Register the subscriptions using `connection->registerSubscriptions()`.

### Open Registration

You can also register through an intermediate LDAP that sends the registration request to the database. This is used when the client cannot have a direct database connection; for example, the client wants to register for an open event while the database is down. This approach is also used when a client wants to register for the same event(s) in multiple databases, concurrently.

[Example 10–17](#) outlines the LDAP open registration using the Oracle Enterprise Security Manager (OESM). Open registration has these prerequisites:

- The client must be an enterprise user
  - In each enterprise domain, create an enterprise role `ENTERPRISE_AQ_USER_ROLE`
  - For each database in the enterprise domain, add a global role `GLOBAL_AQ_USER_ROLE` to enterprise the role `ENTERPRISE_AQ_USER_ROLE`.
  - For each enterprise domain, add an enterprise role `ENTERPRISE_AQ_USER_ROLE` to the privilege group `cn=OracleDBAQUUsers` under `cn=oraclecontext` in the administrative context
  - For each enterprise user that is authorized to register for events in the database, grant enterprise the role `ENTERPRISE_AQ_USER_ROLE`
- The compatibility of the database must be 9.0 or higher
- `LDAP_REGISTRATION_ENABLED` must be set to `TRUE` (default is `FALSE`):
 

```
ALTER SYSTEM SET LDAP_REGISTRATION_ENABLED=TRUE
```
- `LDAP_REG_SYNC_INTERVAL` must be set to the `time_interval` (in seconds) to refresh registrations from LDAP (default is 0, "do not refresh"):

```
ALTER SYSTEM SET LDAP_REG_SYNC_INTERVAL = time_interval
```

To force a database refresh of LDAP registration information immediately, issue this command:

```
ALTER SYSTEM REFRESH LDAP_REGISTRATION
```

**Example 10–17 How to Use Open Registration with LDAP**

1. Create the environment in `Environment::EVENTS | Environment::USE_LDAP` mode.
2. Set the `Environment` object for accessing LDAP:
  - The host and port on which the LDAP server is residing and listening
  - The authentication method; only simple username and password authentication is currently supported
  - The username (distinguished name) and password for authentication with the LDAP server
  - The administrative context for Oracle in the LDAP server
3. Create the `Subscription` object.
4. Set the distinguished names of the databases in which the client wants to receive notifications on the `Subscription` object.
5. Set these `Subscription` attributes.

The namespace can be set to these options:

- To receive notifications from AQ queues, namespace must be set to `Subscription::NS_AQ`. The subscription name is then either of the form `SCHEMA.QUEUE` when registering on a single consumer queue, or `SCHEMA.QUEUE:CONSUMER_NAME` when registering on a multi-consumer queue.
- To receive notifications from other applications that use `conn->postToSubscription()` method, namespace must be set to `Subscription::NS_ANONYMOUS`

The protocol can be set to these options:

- If an OCCI client needs to receive an event notification, this attribute should be set to `Subscription::PROTO_CBK`. You also need to set the notification callback and the subscription context before registering the `Subscription`. The notification callback will be called when the event occurs.
  - For an e-mail notification, set the protocol to `Subscription::PROTO_MAIL`. You must then set the recipient name to the e-mail address to which the notifications will be sent.
  - For an HTTP URL notification, set the protocol to `Subscription::HTTP`. You must set the recipient name to the URL to which the notification will be posted.
  - To invoke PL/SQL procedures in the database on event notification, set protocol to `Subscription::PROTO_SERVER`. You must set the recipient name to the database procedure invoked on notification.
6. Register the subscription: `environment->registerSubscriptions()`.

Open registration will take effect when the database accesses LDAP to pick up new registrations. The frequency of pick-ups is determined by the value of `REG_SYNC_INTERVAL`.

Clients can temporarily disable subscriptions, re-enable them, or permanently unregister from future notifications.

## Notification Callback

The client needs to register a notification callback. This callback is invoked only when there is some activity on the registered subscription. In the Streams AQ namespace, this happens when a message of interest is enqueued.

The callback must return 0, and it must have this specification:

```
typedef unsigned int (*callbackfn) (Subscription &sub, NotifyResult *nr);
```

where:

- `sub` - Subscription object which was used when the callback was registered.
- `nr` - NotifyResult object holding the notification info.

---

**Note:** Ensure that the subscription object used to register for notifications is not destroyed until it explicitly unregisters the subscription.

---

The user can retrieve the payload, message, message id, queue name and consumer name from the `NotifyResult` object, depending on the source of notification. These results are summarized in [Table 10–1](#). Only a bytes payload is currently supported, and you must explicitly dequeue messages from persistent queues in the AQ namespace. If notifications come from non-persistent queues, messages are available to the callback directly; only RAW payloads are supported. If notifications come from persistent queues, the message has to be explicitly dequeued; all payload types are supported.

**Table 10–1 Notification Result Attributes; ANONYMOUS and AQ Namespace**

Notification Result Attribute	ANONYMOUS Namespace	AQ Namespace, Persistent Queue	AQ Namespace, Non-Persistent Queue
payload	valid	invalid	invalid
message	invalid	invalid	valid
messageID	invalid	valid	valid
consumer name	invalid	valid	valid
queue name	invalid	valid	valid

## Message Format Transformation

Applications often use data in different formats, and this requires a type transformation. A transformation is implemented as a SQL function that takes the source data type as input and returns an object of the target data type.

Transformations can be applied when message are enqueued, dequeued, or when they are propagated to a remote subscriber.

**See Also:** The following chapters of the *Oracle Streams Advanced Queuing User's Guide* for information of format transformation:

- Oracle Streams AQ Administrative Interface
- Oracle Streams AQ Administrative Interface: Views
- Oracle Streams AQ Operational Interface: Basic Operations



---

---

## Oracle XA Library

The Oracle XA library is an external interface that allows transaction managers other than the Oracle server to coordinate global transactions. The XA library supports non-Oracle resource managers in distributed transactions. This is particularly useful in transactions between several databases and resources.

The implementation of the Oracle XA library conforms to the X/Open Distributed Transaction Processing (DTP) software architecture's XA interface specification. The Oracle XA Library is installed as part of the Oracle Database Enterprise Edition.

This chapter contains these topics:

- [Application Development with XA and OCCI](#)
- [APIs for XA Support](#)

### See Also:

- <http://www.opengroup.org>
- *Oracle Database Advanced Application Developer's Guide* for more details on the Oracle XA library and architecture
- [Chapter 13, "OCCI Application Programming Interface"](#)

## Application Development with XA and OCCI

For connection, disconnection, and transaction control on Oracle databases, applications must interface with a transaction manager. OCCI has APIs for interacting with `Environment` and `Connection` objects within XA and make them available for Oracle database access, such as `SELECT` queries, DML statements, object access, and so on.

### Example 11–1 How to Use Transaction Managers with XA

```
/* Transaction manager opens connection to the Oracle server*/
tpopen("oracle_xa+acc=p/HR/password+sestm=10", 1, TMNOFLAGS);
/* Transaction manager issues XA commands to start a global transaction*/
tpbegin();

/* Access the underlying Oracle database using OCCI */
Environment *xaenv = Environment::getXAEnvironment(
    "oracle_xa+acc=p/HR/password+sestm=10");
Connection *xaconn = xaenv->getXAConnection(
    "oracle_xa+acc=p/HR/password+sestm=10");

/* Use the Environment & Connection objects */
```

```
Statement *stmt = xaconn->createStatement(  
    "Update Emp set sal = sal * 0.2");  
  
...  
  
/* Release the Environment & Connection objects */  
xaenv->releaseXAConnection(xaconn);  
Environment::releaseXAEnvironment(xaenv);
```

## APIs for XA Support

The following methods of the [Environment Class](#) support use of XA libraries:

- [getXAConnection\(\)](#) on page 13-92
- [releaseXAEnvironment\(\)](#) on page 13-93
- [releaseXAConnection\(\)](#) on page 13-92
- [releaseXAEnvironment\(\)](#) on page 13-93

In addition, the [getXAErrorCode\(\)](#) method of [SQLException Class](#) on page 13-201, should be used by XA enabled applications to determine if thrown exceptions are due to an SQL error (`XA_OK`) or an XA error (an XA error code).

---

---

## Optimizing Performance of OCCI Applications

This chapter describes a few suggestions that will lead to better performance for your OCCI custom applications.

This chapter contains these topics:

- [Transparent Application Failover](#)
- [Connection Sharing](#)
- [Application Managed Data Buffering](#)
- [Array Fetch Using next\(\) Method](#)
- [Modifying Rows Iteratively](#)
- [Runtime Load Balancing of the Stateless Connection Pool](#)
- [Fault Diagnosability](#)

**See Also:**

- [Chapter 13, "OCCI Application Programming Interface"](#)

### Transparent Application Failover

OCCI **Transparent Application Failover** enables OCCI to be more robust in handling database instance failures in distributed applications at run time. If a server node becomes unavailable, applications will automatically reconnect to another surviving node.

Some design options should be considered when including Transparent Application Failover in an application:

- Because of the delays inherent to failover processing, the design of the application may include a notice to the user that a failover is in progress and that normal operation should resume shortly.
- If the session on the initial instance received `ALTER SESSION` commands before the failover began, they will not be automatically replayed on the second instance.

Consequently, the developer may wish to replay these `ALTER SESSION` commands on the second instance.

---

---

**Note:** It is the user's responsibility to track changes to the `SESSION` parameters.

---

---

To address these problems, the application can register a failover callback function. In the event of failover, the callback function is invoked at different times during the course of reestablishing the user's session.

- The first call to the callback function occurs when Oracle first detects an instance connection loss. This callback is intended to allow the application to inform the user of an upcoming delay.
- If failover is successful, a second call to the callback function occurs when the connection is reestablished and usable. At this time the client may wish to replay `ALTER SESSION` commands and inform the user that failover has happened. Note that you must keep track of `SESSION` parameter changes and then replay them after the failover is complete.

If failover is unsuccessful, then the callback function is called to inform the application that failover will not take place.

- An initial attempt at failover may not always be successful. The failover callback should return `FO_RETRY` to indicate that the failover should be attempted again.

**See Also:**

- Definition of `FailOverType` and `FailOverEventType` in [Table 13–11, "Enumerated Values Used by Connection Class"](#) in [Chapter 13, "OCI Application Programming Interface"](#)
- *Oracle Database Net Services Reference* for more detailed information about application failover.

## Using Transparent Application Failover

To enable TAF, the connect string has to be configured for failover and registered on `Connection` (created from `Environment`, `ConnectionPool` and `StatelessConnectionPool`). To register the callback function, use the [Connection Class](#) interface `setTAFNotify()` on page 13-58.

```
void Connection::setTAFNotify(
    int (*notifyFn)(
        Environment *env,
        Connection *conn,
        void *ctx,
        FailOverType foType,
        FailOverEventType foEvent),
    void *ctxTAF);
```

Note that TAF support for `ConnectionPools` does not include `BACKUP` and `PRECONNECT` clauses; these should not be used in the connect string.

## Objects and Transparent Application Failover

Transparent application failover works with the OCI navigational and associative access models and the object cache. In a non Oracle RAC setup, you must ensure that the object type definitions and object OIDs in primary and backup instances are identical.

If the application receives `ORA-25402: transaction must roll back error` after the failover, then it must initiate a rollback to correctly reset the object cache on the client. If a transaction has not started before the failover, the application should still initiate a rollback after the failover to refresh the objects on the client object cache from the new instance.

## Connection Pooling and Transparent Application Failover

If the transparent application failover feature is activated, connections created in a connection pool are also failed over. The application failover callback needs to be specified for each connection obtained from the connection pool; these connections will be failed over when used after the primary instance failure.

## Connection Sharing

This section covers the following topics:

- [Introduction to Thread Safety](#)
- [Implementing Thread Safety](#)
- [Serialization](#)

### Introduction to Thread Safety

Threads are lightweight processes that exist within a larger process. Threads each share the same code and data segments, but have their own program counters, machine registers, and stack. Global and static variables are common to all threads, and a mutual exclusivity mechanism may be required to manage access to these variables from multiple threads within an application.

Once spawned, threads run asynchronously to one another. They can access common data elements and make OCCI calls in any order. Because of this shared access to data elements, a mechanism is required to maintain the integrity of data being accessed by multiple threads. The mechanism to manage data access takes the form of mutexes (mutual exclusivity locks), which ensure that no conflicts arise between multiple threads that are accessing shared resources within an application. In OCCI, mutexes are granted on an OCCI environment basis.

This thread safety feature of the Oracle database server and OCCI library enables developers to use OCCI in a multithreaded application with these added benefits:

- Multiple threads of execution can make OCCI calls with the same result as successive calls made by a single thread.
- When multiple threads make OCCI calls, there are no side effects between threads.
- Even if you do not write a multithreaded program, you do not pay any performance penalty for including thread-safe OCCI calls.
- Use of multiple threads can improve program performance. You can discern gains on multiprocessor systems where threads run concurrently on separate processors, and on single processor systems where overlap can occur between slower operations and faster operations.

In addition to client/server applications, where the client can be a multithreaded program, thread safety is typically used in three-tier or client/agent/server architectures. In this architecture, the client is concerned only with presentation services. The agent (or application server) processes the application logic for the client application. Typically, this relationship is a many-to-one relationship, with multiple clients sharing the same application server.

The server tier in the three-tier architecture is an Oracle database server. The applications server (agent) supports multithreading, with each thread serving a separate client application. In an Oracle environment, this middle-tier application server is an OCCI or precompiler program.

## Implementing Thread Safety

In order to take advantage of thread safety by using OCCI, an application must be running in a thread-safe operating system. Then the application must inform OCCI that the application is running in multithreaded mode by specifying `THREADED_MUTEXED` or `THREADED_UNMUTEXED` for the mode parameter of the `createEnvironment()` method. For example, to turn on mutual exclusivity locking, issue the following statement:

```
Environment *env = Environment::createEnvironment(  
    Environment::THREADED_MUTEXED);
```

Note that once `createEnvironment` is called with `THREADED_MUTEXED` or `THREADED_UNMUTEXED`, all subsequent calls to the `createEnvironment` method must also be made with `THREADED_MUTEXED` or `THREADED_UNMUTEXED` modes.

If a multithreaded application is running in a thread-safe operating system, then the OCCI library will manage mutexes for the application on a for each-OCCI-environment basis. However, you can override this feature and have your application maintain its own mutex scheme. This is done by specifying a mode value of `THREADED_UNMUTEXED` to the `createEnvironment()` method.

---

---

**Note:**

- Applications running on non-thread-safe platforms should not pass a value of `THREADED_MUTEXED` or `THREADED_UNMUTEXED` to the `createEnvironment()` method.
  - If an application is single threaded, whether or not the platform is thread safe, the application should pass a value of `Environment::DEFAULT` to the `createEnvironment` method. This is also the default value for the mode parameter. Single threaded applications which run in `THREADED_MUTEXED` mode may incur performance degradation.
  - OCCI does not support non-blocking mode
- 
- 

## Serialization

As an application programmer, you have two basic options regarding concurrency in a multithreaded application:

- Automatic serialization, in which you utilize OTIS's transparent mechanisms
- Application-provided serialization, in which you manage the contingencies involved in maintaining multiple threads

### Automatic Serialization

In cases where there are multiple threads operating on objects (connections and connection pools) derived from an OCCI environment, you can elect to let OCCI serialize access to those objects. The first step is to pass a value of `THREADED_MUTEXED` to the `createEnvironment` method. At this point, the OCCI library automatically acquires a mutex on thread-safe objects in the environment.

When the OCCI environment is created with `THREADED_MUTEXED` mode, then only the `Environment`, `Map`, `ConnectionPool`, `StatelessConnectionPool` and `Connection` objects are thread-safe. That is, if two threads make simultaneous calls on one of these objects, then OCCI serializes them internally. However, note that all

other OCCI objects, such as `Statement`, `ResultSet`, `SQLException`, `Stream`, and so on, are not thread-safe as, applications should not operate on these objects simultaneously from multiple threads.

Note that the bulk of processing for an OCCI call happens on the server, so if two threads that use OCCI calls go to the same connection, then one of them could be blocked while the other finishes processing at the server.

### Application-Provided Serialization

In cases where there are multiple threads operating on objects derived from an OCCI environment, you can choose to manage serialization. The first step is to pass a value of `THREADED_UNMUTEXED` for the `createEnvironment` mode. In this case the application must mutually exclusively lock OCCI calls made on objects derived from the same OCCI environment. This has the advantage that the mutex scheme can be optimized based on the application design to gain greater concurrency.

When an OCCI environment is created in this mode, OCCI recognizes that the application is running in a multithreaded application, but that OCCI need not acquire its internal mutexes. OCCI assumes that all calls to methods of objects derived from that OCCI environment are serialized by the application. You can achieve this two different ways:

- Each thread has its own environment. That is, the environment and all objects derived from it (connections, connection pools, statements, result sets, and so on) are not shared across threads. In this case your application need not apply any mutexes.
- If the application shares an OCCI environment or any object derived from the environment across threads, then it must serialize access to those objects (by using a mutex, and so on) such that only one thread is calling an OCCI method on any of those objects.

Basically, in both cases, no mutexes are acquired by OCCI. You must ensure that only one OCCI call is in process on any object derived from the OCCI environment at any given time when `THREADED_UNMUTEXED` is used.

---

---

**Note:**

- OCCI is optimized to reuse objects as much as possible. Since each environment has its own heap, multiple environments result in increased consumption of memory. Having multiple environments may imply duplicating work with regard to connections, connection pools, statements, and result set objects. This will result in further memory consumption.
  - Having multiple connections to the server results in more resource consumptions on the server and network. Having multiple environments would normally entail more connections.
- 
- 

## Application Managed Data Buffering

When you provide data for bind parameters by the `set.xxx` methods in parameterized statements, the values are copied into an internal data buffer, and the copied values are then provided to the database server for insertion. To reduce overhead of copying string type data that is available in user buffers, use the `setDataBuffer()` and `next()` methods of the [ResultSet Class](#) and the `execute()` method of the [Statement Class](#).

## setDataBuffer() Method

For high performance applications, OCCI provides the `setDataBuffer` method whereby the data buffer is managed by the application. The following example shows the `setDataBuffer()` method:

```
void setDataBuffer(int paramIndex,
                 void *buffer,
                 Type type,
                 sb4 size,
                 ub2 *length,
                 sb2 *ind = NULL,
                 ub2 *rc = NULL);
```

The following parameters are used in the previous method example:

- `paramIndex`: Parameter number
- `buffer`: Data buffer containing data
- `type`: Type of the data in the data buffer
- `size`: Size of the data buffer
- `length`: Current length of data in the data buffer
- `ind`: Indicator information. This indicates whether the data is NULL or not. For parameterized statements, a value of `-1` means a NULL value is to be inserted. For data returned from callable statements, a value of `-1` means NULL data is retrieved.
- `rc`: Return code. This variable is not applicable to data provided to the `Statement` method. However, for data returned from callable statements, the return code specifies parameter-specific error numbers.

Not all data types can be provided and retrieved by means of the `setDataBuffer()` method. For instance, C++ Standard Library strings cannot be provided with the `setDataBuffer()` interface.

**See Also:** [Table 5-2, "External Data Types and Corresponding C++ and OCCI Types"](#) in [Chapter 5, "Data Types"](#) for specific cases

There is an important difference between the data provided by the `setxxx()` methods and `setDataBuffer()` method. When data is copied in the `setxxx()` methods, the original can change once the data is copied. For example, you can use a `setString(str1)` method, then change the value of `str1` prior to execute. The value of `str1` that is used is the value at the time `setString(str1)` is called. However, for data provided by means of the `setDataBuffer()` method, the buffer must remain valid until the execution is completed.

If iterative executes or the `executeArrayUpdate()` method is used, then data for multiple rows and iterations can be provided in a single buffer. In this case, the data for the *i*th iteration is at `buffer + (i-1) * size` address and the length, indicator, and return codes are at `*(length + i)`, `*(ind + i)`, and `*(rc + i)` respectively.

This interface is also meant for use with array executions and callable statements that have array or OUT bind parameters.

The same method is available in the `ResultSet` class to retrieve data without re-allocating the buffer for each fetch.



## executeArrayUpdate() Method

If all data is provided with the `setDataBuffer()` methods or output streams (that is, no `setxxx()` methods besides `setDataBuffer()` or `getStream()` are called), then there is a simplified way of doing iterative execution.

In this case, you should not call `setMaxIterations()` and `setMaxParamSize()`. Instead, call the `setDataBuffer()` or `getStream()` method for each parameter with the appropriate size arrays to provide data for each iteration, followed by the `executeArrayUpdate(int arrayLength)` method. The `arrayLength` parameter specifies the number of elements provided in each buffer. Essentially, this is same as setting the number of iterations to `arrayLength` and executing the statement.

Since the stream parameters are specified only once, they can be used with `array` executes as well. However, if any `setxxx()` methods are used, then the `addIteration()` method is called to provide data for multiple rows. To compare the two approaches, consider [Example 12-1](#) that inserts two employees in the `emp` table:

### Example 12-1 How to Insert Records Using the `addIteration()` method

```
Statement *stmt = conn->createStatement(
    "insert into departments (department_id, department_name) values(:1, :2)");
char dnames[][100] = {"Community Outreach", "University Recruiting"};
ub2 dnameLen[2];

for (int i = 0; i < 2; i++)
    dnameLen[i] = strlen(dnames[i] + 1);

stmt->setMaxIterations(2);    // set maximum number of iterations

stmt->setInt(1, 7369);        // specify data for the first row
stmt->setDataBuffer(2, dnames, OCCI_SQLT_STR, sizeof(dnames[0]), dnameLen);
stmt->addIteration();

stmt->setInt(1, 7654);        // specify data for the second row
// a setDataBuffer is unnecessary for the second
// bind parameter as data provided through
// setDataBuffer is specified only once.

stmt->executeUpdate();
```

However, if the first parameter could also be provided through the `setDataBuffer()` interface, then, instead of the `addIteration()` method, you would use the `executeArrayUpdate()` method, as shown in [Example 12-2](#):

### Example 12-2 How to Insert Records Using the `executeArrayUpdate()` Method

```
Statement *stmt = conn->createStatement(
    "insert into departments (department_id, department_name) values(:1, :2)");
char dnames[][100] = {"Community Outreach", "University Recruiting"};
ub2 dnameLen[2];

for (int i = 0; i < 2; i++)
    dnameLen[i] = strlen(dnames[i] + 1);

int ids[2] = {7369, 7654};
ub2 idLen[2] = {sizeof(ids[0]), sizeof(ids[1])};
stmt->setDataBuffer(1, ids, OCCI_INT, sizeof(ids[0]), idLen);
stmt->setDataBuffer(2, dnames, OCCI_SQLT_STR, sizeof(dnames[0]), dnameLen);

stmt->executeArrayUpdate(2);    // data for two rows is inserted.
```

## Array Fetch Using next() Method

If the application is fetching data with only the `setDataBuffer()` interface or the stream interface, then an array fetch can be executed. The array fetch is implemented through the `next()` method of the `ResultSet` class. You must process the results obtained through `next()` before calling it again.

### Example 12–3 How to use Array Fetch with a ResultSet

```
ResultSet *resultSet = stmt->executeQuery(...);
resultSet->setDataBuffer(...);
while (resultSet->next(numRows) == DATA_AVAILABLE)
    process(resultSet->getNumArrayRows());
```

This causes up to `numRows` amount of data to be fetched for each column. The buffers specified with the `setDataBuffer()` interface should be large enough to hold at least `numRows` of data.

## Modifying Rows Iteratively

To process batch errors, specify that the `Statement` object is in a `batchMode` of execution using the `setBatchErrorMode()` method. Once the `batchMode` is set and a batch update runs, any resulting errors are reported through the [BatchSQLException Class](#).

The `BatchSQLException` class provides methods that handle batch errors.

[Example 12–4](#) illustrates how batch handling can be implemented within any OCI application.

### Example 12–4 How to Modify Rows Iteratively and Handle Errors

1. Create the `Statement` object and set its batch error mode to `TRUE`.

```
Statement *stmt = conn->createStatement (...);
stmt->setBatchErrorMode (true);
```

2. Perform programmatic changes necessary by the application.
3. Update the statement.

```
try {
    updateCount = stmt->executeUpdate ();
}
```

4. Catch and handle any errors generated during the batch insert or update.

```
catch (BatchSQLException &batchEx)
{
    cout<<"Batch Exception: "<<batchEx.what()<<endl;
    int errCount = batchEx.getFailedRowCount();
    cout << "Number of rows failed " << errCount <<endl;
    for (int i = 0; i < errCount; i++)
    {
        SQLException err = batchEx.getException(i);
        unsigned int rowIndex = batchEx.getRowNum(i);
        cout<<"Row " << rowIndex << " failed because of "
            << err.getErrorCode() << endl;
    }
    // take recovery action on the failed rows
}
```

5. Catch and handle other errors generated during the statement update. Note that statement-level errors are still thrown as instances of a `SQLException`.

```
catch( SQLException &ex) // to catch other SQLExceptions.
{
    cout << "SQLException: " << e.what() << endl;
}
```

## Runtime Load Balancing of the Stateless Connection Pool

Runtime load balancing in a stateless connection pool dynamically routes connection request to the least loaded instance of the database. This is achieved through the use of service metrics distributed by the Oracle RAC load-balancing advisory.

The feature modifies the stateless connection pool in the following ways:

- The pool receives periodic notifications about the instance load.
- When a request for a connection is received, the pool picks the best possible connection for the type of request, based on the load of the instance.
- The stateless connection pool periodically terminates connections of overloaded instances, maintaining the connection topology that corresponds to the instance load.
- Since the connections to overloaded instances may be terminated, the pool creates new connections to maintain the concurrency requirement. These new connections are created using the connect-time load balancing of the Oracle RAC listener.

Runtime load balancing is turned on by default when the OCCI environment is created in `THREADED_MUTEXED` and `EVENTS` modes, and when the server is configured to issue event notifications.

**See Also:** *Oracle Call Interface Programmer's Guide*

## API Support

New `NO_RLB` option for the `PoolType` attribute of the [StatelessConnectionPool Class](#) on page 13-202 disables runtime load balancing.

## Fault Diagnosability

Fault diagnosability captures diagnostic data, such as dump files or core dump files, on the OCCI client when a problem incident occurs. For each incident, the fault diagnosability feature creates an Automatic Diagnostic Repository (ADR) subdirectory for storing this diagnostic data. For example, if either a Linux or a UNIX application fails with a null pointer reference, then the core file appears in the ADR home directory (if it exists), not in the operating system directory. This section discusses the ADR subdirectory structure and the utility to manage its output, the ADR Command Interpreter (ADRCI).

An ADR home is the root directory for all diagnostic data for an instance of a product, such as OCCI, and a particular operating system user. All ADR homes appear under the same root directory, the ADR base.

**See Also:** *Oracle Database Administrator's Guide*, "Managing Diagnostic Data"

## ADR Base Location

The location of the ADR base is determined in the following order:

1. In the `sqlnet.ora` file (on *Windows*, in the `%TNS_ADMIN%` directory, or on *Linux* or *Unix*, in the `$TNS_ADMIN` directory).

If there is no `TNS_ADMIN` directory, then `sqlnet.ora` is stored in the current directory.

If the ADR base is listed in the `sqlnet.ora` file, it is a statement of the type:

```
ADR_BASE=/directory/adr
```

where:

- `adr` is a directory that must already exist and be writable by all operating system users who execute OCCI applications and want to share the same ADR base.
- `directory` is the path name

If `ADR_BASE` is set, and if all users share a single `sqlnet.ora` file, then OCCI stops searching when directory `adr` does not exist or if it is not writable by the user. If `ADR_BASE` is not set, then OCCI continues the search, testing for the existence of other specific directories.

For example, if `sqlnet.ora` contains the entry `ADR_BASE=/home/chuck/test` then:

- ADR base is:  
`/home/chuck/test/oradiag_chuck`
- ADR home may be:  
`/home/chuck/test/oradiag_chuck/diag/clients/user_chuck/host_4144260688_11`

2. If the Oracle base exists (on *Windows*: `%ORACLE_BASE%`, or on *Linux* and *Unix*: `$ORACLE_BASE`), the client subdirectory also exists because it is created by the Oracle Universal Installer when the database is installed.

For example, if `$ORACLE_BASE` is `/home/chuck/obase`, then:

- ADR base is:  
`/home/chuck/obase`
- ADR home may be:  
`/home/chuck/obase/diag/clients/user_chuck/host_4144260688_11`

3. If the Oracle home exists (on *Windows*: `%ORACLE_HOME%`, or on *Linux* and *Unix*: `$ORACLE_HOME`), the client subdirectory also exists because it is created by the Oracle Universal Installer when the database is installed.

For example, if `$ORACLE_HOME` is `/ade/chuck_11/oracle`, then:

- ADR base is:  
`/ade/chuck_11/oracle/log`
- ADR home may be:  
`/ade/chuck_11/oracle/log/diag/clients/user_chuck/host_4144260688_11`

4. On the operating system home directory.
  - On *Windows*, the operating system home directory is `%USERPROFILE%`.

The location of folder Oracle is at:

```
C:\Documents and Settings\chuck
```

If the application runs as a service, the home directory option is skipped.

- On *Linux* and *Unix*, the operating system home directory is  $\$HOME$ .

The location may be:

```
/home/chuck/oradiag_chuck
```

For example, in an Instant Client, if  $\$HOME$  is `/home/chuck`, then:

- ADR base is:

```
/home/chuck/oradiag_chuck
```

- ADR home may be:

```
/home/chuck/oradiag_chuck/diag/clients/user_chuck/host_4144260688_11
```

**See Also:** ["Instant Client"](#) on page 2-2

#### 5. In the temporary directory.

- On *Windows*, the temporary directories are searched in the following order:

- %TMP%
- %TEMP%
- %USERPROFILE%
- Windows system directory

- On *Linux* and *Unix*, the temporary directory is in `/var/tmp`.

For example, in an Instant Client, if  $\$HOME$  is not writable, then:

- ADR base is:

```
/var/tmp/oradiag_chuck
```

- ADR home may be:

```
/var/tmp/oradiag_chuck/diag/clients/user_chuck/host_4144260688_11
```

If none of these directory choices are available and writable, ADR will not be created and diagnostics will not be stored.

**See Also:** *Oracle Database Net Services Reference*

## Using ADRCI

ADRCI is a command-line tool that enables you to view diagnostic data within the ADR, and to package incident and problem information into a zip file that can be shared with Oracle Support. ADRCI can be used either interactively and through a script.

A **problem** is a critical error in OCI or the client. Each problem has a problem key. An **incident** is a single occurrence of a problem, and it is identified by a unique numeric incident ID. Each incident has a problem key which has a set of attributes: the ORA error number, error parameter values, and similar information. Two incidents have the same root cause if their problem keys match.

The following examples demonstrate how to use ADRCI on a Linux operating system. Note that ARDCI commands are case-insensitive. All user input is in bold typeface.

**Example 12-5 How to Use ADRCI for OCCI Application Incidents**

To launch ADRCI in a Linux system, use the `adrci` command. Once ADRCI starts, find out the particulars of the `show base` command with `help`, and then determine the base of a particular client using the `-product client` option (necessary for OCCI applications). To set the ADRCI base, use the `set base` command. Once ADRCI starts, then the default ADR base is for the `rdbms` server. The `$ORACLE_HOME` is set to `/ade/chuck_13/oracle`. To view the incidents, use the `show incidents` command. To exit ADRCI, use the `quit` command.

```
% adrci
```

```
ADRCI: Release 11.1.0.6.0 - on Wed July 25 16:16:55 2007
```

```
Copyright (c) 1982, 2007, Oracle. All rights reserved.
```

```
adrci> help show base
```

```
Usage: SHOW BASE [-product <product_name>]
```

```
Purpose: Show the current ADR base setting.
```

```
Options:
```

```
[-product <product_name>]: This option allows users to show the  
given product's ADR Base location. The current registered products are  
"CLIENT" and "ADRCI".
```

```
Examples:
```

```
show base -product client  
show base
```

```
adrci> show base -product client
```

```
ADR base is "/ade/chuck_13/oracle/log"
```

```
adrci> help set base
```

```
Usage: SET BASE <base_str>
```

```
Purpose: Set the ADR base to use in the current ADRCI session.
```

```
If there are valid ADR homes under the base, all homes will  
will be added to the current ADRCI session.
```

```
Arguments:
```

```
<base_str>: It is the ADR base directory, which is a system-dependent  
directory path string.
```

```
Notes:
```

```
On platforms that use "." to signify current working directory,  
it can be used as base_str.
```

```
Example:
```

```
set base /net/sttttdl/scratch/someone/view_storage/someone_v1/log  
set base .
```

```
adrci> set base /ade/chuck_13/oracle/log
```

```
adrci> show incidents
```

```
...
adrci> quit
```

### Example 12-6 How to Use ADRCI for Instant Client

Because Instant Client does not use `$ORACLE_HOME`, the default ADR base is the user's home directory.

```
adrci> show base -product client
ADR base is "/home/chuck/oradiag_chuck"
adrci> set base /home/chuck/oradiag_chuck
adrci> show incidents
```

```
ADR Home = /home/chuck/oradiag_chuck/diag/clients/user_chuck/host_4144260688_11:
*****
```

INCIDENT_ID	PROBLEM_KEY	CREATE_TIME
1	oci 24550 [6]	2007-05-01 17:20:02.803697 -07:00

1 rows fetched

```
adrci> quit
```

#### See Also:

- *Oracle Database Utilities* for an introduction to the ADRCI
- ["Instant Client"](#) on page 2-2

## Controlling ADR Creation and Disabling Fault Diagnosability

To disable the fault diagnosability feature, you must turn off the capture of diagnostics. Edit the `sqlnet.ora` file by changing the values of the `DIAG_ADR_ENABLED` and `DIAG_DDE_ENABLED` parameters to `FALSE`; the default values are `TRUE`.

To turn off the OCCI signal handler and to re-enable standard operating system failure processing, edit the `sqlnet.ora` file by adding the corresponding parameter: `DIAG_SIGHANDLER_ENABLED=FALSE`.

**See Also:** *Oracle Database Net Services Reference*





---

---

# OCCI Application Programming Interface

This chapter describes the OCCI classes and methods for C++.

**See Also:**

- Format Models in *Oracle Database SQL Language Reference*
- Table A-1 in *Oracle Database Globalization Support Guide*

## OCCI Classes and Methods

Table 13–1 provides a brief description of all the OCCI classes. This section is followed by detailed descriptions of each class and its methods.

**Table 13–1 Summary of OCCI Classes**

Class	Description
<a href="#">Agent Class</a> on page 13-7	Represents an agent in the Advanced Queuing context.
<a href="#">AnyData Class</a> on page 13-10	Provides methods for the Object Type Translator (OTT) utility, read and write SQL methods for linearization of objects, and conversions to and from other data types.
<a href="#">BatchSQLException Class</a> on page 13-19	Provides methods for handling batch processing errors; extends the <a href="#">SQLException Class</a> .
<a href="#">Bfile Class</a> on page 13-20	Provides access to a SQL <code>BFILE</code> value.
<a href="#">Blob Class</a> on page 13-26	Provides access to a SQL <code>BLOB</code> value.
<a href="#">Bytes Class</a> on page 13-34	Examines individual bytes of a sequence for comparing bytes, searching bytes, and extracting bytes.
<a href="#">Clob Class</a> on page 13-37	Provides access to a SQL <code>CLOB</code> value.
<a href="#">Connection Class</a> on page 13-48	Represents a connection with a specific database.
<a href="#">ConnectionPool Class</a> on page 13-62	Represents a connection pool with a specific database.
<a href="#">Consumer Class</a> on page 13-67	Supports dequeuing of <code>Messages</code> and controls the dequeuing options.
<a href="#">Date Class</a> on page 13-75	Specifies abstraction for SQL <code>DATE</code> data items. Also provides formatting and parsing operations to support the OCCI escape syntax for date values.
<a href="#">Environment Class</a> on page 13-85	Provides an OCCI environment to manager memory and other resources of OCCI objects. An OCCI driver manager maps to an OCCI environment handle.
<a href="#">IntervalDS Class</a> on page 13-97	Represents a period of time in terms of days, hours, minutes, and seconds.
<a href="#">IntervalYM Class</a> on page 13-107	Represents a period of time in terms of year and months.
<a href="#">Listener Class</a> on page 13-116	Listens on behalf of one or more agents on one or more queues.
<a href="#">Map Class</a> on page 13-118	Used to store the mapping of the SQL structured type to C++ classes.
<a href="#">Message Class</a> on page 13-119	A unit that is enqueued or dequeued.
<a href="#">MetaData Class</a> on page 13-127	Used to determine types and properties of columns in a <code>ResultSet</code> , that of existing schema objects in the database, or the database as a whole.
<a href="#">NotifyResult Class</a> on page 13-141	Used to hold notification information from the Streams AQ callback function.
<a href="#">Number Class</a> on page 13-142	Models the numerical data type.

**Table 13–1 (Cont.) Summary of OCCI Classes**

Class	Description
<a href="#">PObject Class</a> on page 13-161	When defining types, enables specification of persistent or transient instances. Class instances derived from <code>PObject</code> can be either persistent or transient. If persistent, a class instance derived from <code>PObject</code> inherits from the <code>PObject</code> class; if transient, there is no inheritance.
<a href="#">Producer Class</a> on page 13-167	Supports enqueueing options and enqueues <code>Messages</code> .
<a href="#">Ref Class</a> on page 13-172	The mapping in C++ for the SQL REF value, which is a reference to a SQL structured type value in the database.
<a href="#">RefAny Class</a> on page 13-177	The mapping in C++ for the SQL REF value, which is a reference to a SQL structured type value in the database.
<a href="#">ResultSet Class</a> on page 13-180	Provides access to a table of data generated by executing an OCCI <code>Statement</code> .
<a href="#">SQLException Class</a> on page 13-199	Provides information on database access errors.
<a href="#">StatelessConnectionPool Class</a> on page 13-202	Represents a pool of stateless, authenticated connections to the database.
<a href="#">Statement Class</a> on page 13-212	Used for executing SQL statements, including both query statements and insert / update / delete statements.
<a href="#">Stream Class</a> on page 13-253	Used to provide streamed data (usually of the LONG data type) to a prepared DML statement or stored procedure call.
<a href="#">Subscription Class</a> on page 13-256	Encapsulates the information and operations necessary for registering a subscriber for notification.
<a href="#">Timestamp Class</a> on page 13-263	Specifies abstraction for SQL <code>TIMESTAMP</code> data items. Also provides formatting and parsing operations to support the OCCI escape syntax for time stamp values.

## Using OCCI Classes

OCCI classes are defined in the `oracle::occi` namespace. An OCCI class name within the `oracle::occi` namespace can be referred to in one of three ways:

- Use the scope resolution operator (`::`) for each OCCI class name.
- Use the using declaration for each OCCI class name.
- Use the using directive for all OCCI class name.

### Using Scope Resolution Operator for OCCI

The scope resolution operator (`::`) is used to explicitly specify the `oracle::occi` namespace and the OCCI class name. To declare `myConnection`, a `Connection` object, using the scope resolution operator, you would use the following syntax:

```
oracle::occi::Connection myConnection;
```

### Using Declaration in OCCI

The using declaration is used when the OCCI class name can be used in a compilation unit without conflict. To declare the OCCI class name in the `oracle::occi` namespace, you would use the following syntax:

```
using oracle::occi::Connection;
```

Connection now refers to `oracle::occi::Connection`, and `myConnection` can be declared as `Connection myConnection;`.

## Using Directive in OCCI

The `using` directive is used when all OCCI class names can be used in a compilation unit without conflict. To declare all OCCI class names in the `oracle::occi` namespace, you would use the following syntax:

```
using oracle::occi;
```

Then, just as with the `using` declaration, the following declaration would now refer to the OCCI class `Connection` as `Connection myConnection;`.

## Using Advanced Queuing in OCCI

The Advanced Queuing classes `Producer`, `Consumer`, `Message`, `Agent`, `Listener`, `Subscription` and `NotifyResult` are defined in `oracle::occi::aq` namespace.

## OCCI Support for Windows NT and z/OS

When building OCCI application on Windows, a preprocessor definition for `WIN32COMMON` has to be added.

The following global methods are designed for accessing collections of `Refs` in [ResultSet Class](#) and [Statement Class](#) on Windows NT and z/OS. While method names changed, the number of parameters and their types remain the same.

- Use `getVectorOfRefs()` in place of `getVector()` on Windows NT and z/OS.
- Use `setVectorOfRefs()` in place of `setVector()` on Windows NT and z/OS.

Applications on Windows NT and z/OS should be calling these new methods only for retrieving and inserting collections of references. Applications not running on Windows NT or z/OS can use either set of accessors. However, Oracle recommends the use of the new methods for any vector operations with `Refs`.

## Working with Collections of Refs

Collections of `Refs` can be fetched and inserted using methods of the following classes:

### ResultSet Class

**Fetching Collection of Refs** Use the following version of [getVectorOfRefs\(\)](#) on page 13-193 to return a column of references:

```
void getVectorOfRefs(
    ResultSet *rs,
    unsigned int index,
    vector<Ref<T> > &vect);
```

### Statement Class

**Fetching Collection of Refs** Use [getVectorOfRefs\(\)](#) on page 13-229 to return a collection of references from a column:

```
void getVectorOfRefs(
    Statement *stmt,
    unsigned int index,
    vector<Ref<T> > &vect);
```

**Inserting a Collection of Refs** Use `setVectorOfRefs()` on page 13-251 to insert a collection of references into a column:

```
template <class T>
void setVectorOfRefs(
    Statement *stmt,
    unsigned int paramIndex,
    const vector<Ref<T> > &vect,
    const string &sqltype);
```

**Inserting a Collection of Refs: Multibyte Support** The following method should be used for multibyte support:

```
void setVectorOfRefs(
    Statement *stmt,
    unsigned int paramIndex,
    const vector<Ref<T> > &vect,
    const string &schemaName,
    const string &typeName);
```

**Inserting a Collection of Refs: UString (UTF16) Support** The following method should be used for UString support:

```
template <class T>
void setVectorOfRefs(
    Statement *stmt,
    unsigned int paramIndex,
    const vector<Ref<T> > &vect,
    const UString &schemaName,
    const UString &typeName);
```

## Common OCCI Constants

Table 13–2 defines the common constants used by all OCCI classes. Constants that are defined for use within specific classes are summarized at the beginning of class-specific sections.

**Table 13–2 Enumerated Values Used by All OCCI Classes**

Attribute	Options
LockOptions	<ul style="list-style-type: none"><li>▪ <code>OCCI_LOCK_NONE</code> clears the lock setting on the <code>Ref</code> object.</li><li>▪ <code>OCCI_LOCK_X</code> indicates that the object should be locked, and to wait for the lock to be available if the object is locked by another session.</li><li>▪ <code>OCCI_LOCK_X_NOWAIT</code> indicates that the object should be locked, and returns an error if it is locked by another session.</li></ul>
CharSetForm	<ul style="list-style-type: none"><li>▪ <code>OCCI_SQLCS_IMPLICIT</code> indicates that the local database character set should be used.</li><li>▪ <code>OCCI_SQLCS_NCHAR</code> indicates that the local database NCHAR set should be used.</li><li>▪ <code>OCCI_SQLCS_EXPLICIT</code> indicates that the character set is specified explicitly.</li><li>▪ <code>OCCI_SQLCS_FLEXIBLE</code> means that the character set is a PL/SQL flexible parameter.</li></ul>
ReturnStatus	<ul style="list-style-type: none"><li>▪ <code>OCCI_SUCCESS</code> indicates that the call has been made successfully (transaction failover mode).</li><li>▪ <code>FO_RETRY</code> indicates that the call should be retried (transaction failover mode).</li></ul>

## Agent Class

The `Agent` class represents an agent in the Advanced Queuing context.

**Table 13–3 Summary of Agent Methods**

Method	Summary
<a href="#">Agent()</a> on page 13-7	Agent class constructor.
<a href="#">getAddress()</a> on page 13-7	Returns the address of the <code>Agent</code> .
<a href="#">getName()</a> on page 13-8	Returns the name of the <code>Agent</code> .
<a href="#">getProtocol()</a> on page 13-8	Returns the protocol of the <code>Agent</code> .
<a href="#">isNull()</a> on page 13-8	Tests whether the <code>Agent</code> object is <code>NULL</code> .
<a href="#">operator=()</a> on page 13-8	Assignment operator for <code>Agent</code> .
<a href="#">setAddress()</a> on page 13-8	Sets address of the <code>Agent</code> object.
<a href="#">setName()</a> on page 13-9	Sets name of the <code>Agent</code> object.
<a href="#">setNull()</a> on page 13-9	Sets <code>Agent</code> object to <code>NULL</code> .
<a href="#">setProtocol()</a> on page 13-9	Sets protocol of the <code>Agent</code> object.

## Agent()

Agent class constructor.

Syntax	Description
<code>Agent(   const Environment *env);</code>	Creates an <code>Agent</code> object initialized to its default values.
<code>Agent(   const Agent&amp; agent);</code>	Copy constructor.
<code>Agent(   const Environment *env,   const string&amp; name,   const string&amp; address,   unsigned int protocol = 0);</code>	Creates an <code>Agent</code> object with specified <code>Agent</code> 's name, address, and protocol.

Parameter	Description
<code>env</code>	Environment
<code>name</code>	Name
<code>agent</code>	Original agent
<code>address</code>	Address
<code>protocol</code>	Protocol

## getAddress()

Returns a string containing `Agent`'s address.

**Syntax**

```
string getAddress() const;
```

**getName()**

Returns a string containing Agent's name.

**Syntax**

```
string getName() const;
```

**getProtocol()**

Returns a numeric code representing Agent's protocol.

**Syntax**

```
unsigned int getProtocol() const;
```

**isNull()**

Tests whether the Agent object is NULL. If the Agent object is NULL, then TRUE is returned; otherwise, FALSE is returned.

**Syntax**

```
bool isNull() const;
```

**operator=()**

Assignment operator for Agent class.

**Syntax**

```
void operator=(  
const Agent& agent);
```

---

Parameter	Description
agent	The original Agent object.

---

**setAddress()**

Sets the address of the Agent object.

**Syntax**

```
void setAddress(  
const string& addr);
```

---

Parameter	Description
addr	The name of the Agent object.

---



## setName()

Sets the name of the Agent object.

### Syntax

```
void setName(  
    const string& name);
```

Parameter	Description
name	The name of the Agent object.

## setNull()

Sets the Agent object to NULL. Unless operating in an inner scope, this call should be made before terminating the Connection used to create this Agent.

### Syntax

```
void setNull();
```

## setProtocol()

Sets the protocol of the Agent object.

### Syntax

```
void setProtocol(  
    unsigned int protocol = 0);
```

Parameter	Description
protocol	The protocol of the Agent object.

## AnyData Class

The `AnyData` class models self-descriptive data by encapsulating the type information with the actual data. `AnyData` is used primarily with OCCI Advanced Queuing feature, to represent and enqueue data and to receive messages from queues as `AnyData` instances.

Most SQL and user-defined types can be converted into an `AnyData` type using the `setFromxxx()` methods. An `AnyData` object can be converted into most SQL and user-defined types using `getAsxxx()` methods. `SYS.ANYDATA` type models `AnyData` both in SQL and PL/SQL.

---

---

**Note:** See [Table 13–4, "OCCI Data Types supported by AnyData Class"](#) for supported data types.

---

---

The `getType()` call returns the `TypeCode` represented by an `AnyData` object, while the `isNull()` call determines if `AnyData` contains a `NULL` value. The `setNull()` method sets the value of `AnyData` to `NULL`.

To use the OCCI `AnyData` type, the environment has to be initiated in `OBJECT` mode.

### **Example 13–1 Converting From an SQL Pre-Defined Type To AnyData Type**

This example demonstrates how to convert types from `string` to `AnyData`.

```
Connection *conn;
...
AnyData any(conn);
string str("Hello World");
any.setFromString(str);
...
```

### **Example 13–2 Creating an SQL Pre-Defined Type From AnyData Type**

This example demonstrates how to convert an `AnyData` object back to a `string` object. Note the use of `getType()` and `isNull()` methods to validate `AnyData` prior to conversion.

```
Connection *conn;
string str;
...
if(!any.isNull())
{   if(any.getType()==OCCI_TYPECODE_VARCHAR2)
    {
        str = any.getAsString();
        cout<<str;
    }
}
...
```

### **Example 13–3 Converting From a User-Defined Type To AnyData Type**

This example demonstrates how to convert from a user-defined type to `AnyData` type.

```
Connection *conn;
...
// Assume an OBJECT of type Person with the following defined fields
// CREATE TYPE person as OBJECT (
```

```

//   FRIST_NAME VARCHAR2(20),
//   LAST_NAME VARCHAR2(25),
//   EMAIL VARCHAR2(25),
//   SALARY NUMBER(8,2)
// );
// Assume relevant classes have been generated by OTT.
...
Person *pers new Person( "Steve", "Addams",
                        "steve.addams@anycompany.com", 50000.00);
AnyData anyObj(conn);
anyObj.setFromObject(pers);
...

```

#### **Example 13–4 Converting From a User-Defined Type To AnyData Type**

This example demonstrates how to convert an AnyData object back to a user-defined type. Note the use of `getType()` and `isNull()` methods to validate AnyData prior to conversion.

```

Connection *conn;
// Assume an OBJECT of type Person with the following defined fields
// CREATE TYPE person as OBJECT (
//   FRIST_NAME VARCHAR2(20),
//   LAST_NAME VARCHAR2(25),
//   EMAIL VARCHAR2(25),
//   SALARY NUMBER(8,2)
// );
// Assume relevant classes have been generated by OTT.
Person *pers = new Person();
...
If(!anyObj.isNull())
{   if(anyObj.getType()==OCCI_TYPECODE_OBJECT)
    pers = anyObj.getAsObject();
}
...

```

**Table 13–4 OCCI Data Types supported by AnyData Class**

Data Type	TypeCode
BDouble	OCCI_TYPECODE_BDOUBLE
BFile	OCCI_TYPECODE_BFILE
BFloat	OCCI_TYPECODE_BFLOAT
Bytes	OCCI_TYPECODE_RAW
Date	OCCI_TYPECODE_DATE
IntervalDS	OCCI_TYPECODE_INTERVAL_DS
IntervalYM	OCCI_TYPECODE_INTERVAL_YM
Number	OCCI_TYPECODE_NUMBERB
PObject	OCCI_TYPECODE_OBJECT
Ref	OCCI_TYPECODE_REF
string	OCCI_TYPECODE_VARCHAR2
TimeStamp	OCCI_TYPECODE_TIMESTAMP

**Table 13–5 Summary of AnyData Methods**

Method	Summary
<a href="#">AnyData()</a> on page 13-12	AnyData class constructor.
<a href="#">getAsBDouble()</a> on page 13-13	Converts an AnyData object into BDouble.
<a href="#">getAsBfile()</a> on page 13-13	Converts an AnyData object into Bfile.
<a href="#">getAsBFloat()</a> on page 13-13	Converts an AnyData object into BFloat.
<a href="#">getAsBytes()</a> on page 13-13	Converts an AnyData object into Bytes.
<a href="#">getAsDate()</a> on page 13-13	Converts an AnyData object into Date.
<a href="#">getAsIntervalDS()</a> on page 13-13	Converts an AnyData object into IntervalDS.
<a href="#">getAsIntervalYM()</a> on page 13-14	Converts an AnyData object into IntervalYM.
<a href="#">getAsNumber()</a> on page 13-14	Converts an AnyData object into Number.
<a href="#">getAsObject()</a> on page 13-14	Converts an AnyData object into PObject.
<a href="#">getAsRef()</a> on page 13-14	Converts an AnyData object into RefAny.
<a href="#">getAsString()</a> on page 13-14	Converts an AnyData object into a namespace string.
<a href="#">getAsTimestamp()</a> on page 13-14	Converts an AnyData object into Timestamp.
<a href="#">getType()</a> on page 13-14	Retrieves the data type held by the AnyData object. See <a href="#">Table 13–4</a> .
<a href="#">isNull()</a> on page 13-15	Tests whether AnyData object is NULL.
<a href="#">setFromBDouble()</a> on page 13-15	Converts a BDouble into Anydata.
<a href="#">setFromBfile()</a> on page 13-15	Converts a Bfile into Anydata.
<a href="#">setFromBFloat()</a> on page 13-15	Converts a BFloat into Anydata.
<a href="#">setFromBytes()</a> on page 13-16	Converts a Bytes into Anydata.
<a href="#">setFromDate()</a> on page 13-16	Converts a Date into Anydata.
<a href="#">setFromIntervalDS()</a> on page 13-16	Converts an IntervalDS into Anydata.
<a href="#">setFromIntervalYM()</a> on page 13-16	Converts an IntervalYM into Anydata.
<a href="#">setFromNumber()</a> on page 13-17	Converts a Number into Anydata.
<a href="#">setFromObject()</a> on page 13-17	Converts a PObject into Anydata.
<a href="#">setFromRef()</a> on page 13-17	Converts a RefAny into Anydata.
<a href="#">setFromString()</a> on page 13-17	Converts a namespace string into Anydata.
<a href="#">setFromTimestamp()</a> on page 13-18	Converts a Timestamp into Anydata.
<a href="#">setNull()</a> on page 13-18	Sets AnyData object to NULL.

## AnyData()

AnyData constructor.

### Syntax

```
AnyData(
    const Connection *conn);
```

---

Parameter	Description
conn	The connection.

---

## getAsBDouble()

Converts an AnyData object into BDouble.

### Syntax

```
BDouble getAsBDouble() const;
```

## getAsBfile()

Converts an AnyData object into Bfile.

### Syntax

```
Bfile getAsBfile() const;
```

## getAsBFloat()

Converts an AnyData object into BFloat.

### Syntax

```
BFloat getAsBFloat() const;
```

## getAsBytes()

Converts an AnyData object into Bytes.

### Syntax

```
Bytes getAsBytes() const;
```

## getAsDate()

Converts an AnyData object into Date.

### Syntax

```
Date getAsDate() const;
```

## getAsIntervalDS()

Converts an AnyData object into IntervalDS.

### Syntax

```
IntervalDS getAsIntervalDS() const;
```

## getAsIntervalYM()

Converts an AnyData object into IntervalYM.

### Syntax

```
IntervalYS getAsIntervalYM() const;
```

## getAsNumber()

Converts an AnyData object into Number.

### Syntax

```
Number getAsNumber() const;
```

## getAsObject()

Converts an AnyData object into PObject.

### Syntax

```
PObject* getAsObject() const;
```

## getAsRef()

Converts an AnyData object into RefAny.

### Syntax

```
RefAny getAsRef() const;
```

## getAsString()

Converts an AnyData object into a namespace string.

### Syntax

```
string getAsString() const;
```

## getAsTimestamp()

Converts an AnyData object into Timestamp.

### Syntax

```
Timestamp getAsTimestamp() const;
```

## getType()

Retrieves the data type held by the AnyData object. Refer to [Table 13-4](#) on page 13-11 for valid values for TypeCode.

**Syntax**

```
TypeCode getType();
```

**isNull()**

Tests whether the AnyData object is NULL. If the AnyData object is NULL, then TRUE is returned; otherwise, FALSE is returned.

**Syntax**

```
bool isNull() const;
```

**setFromBDouble()**

Converts a BDouble into AnyData.

**Syntax**

```
void setFromBDouble(
    const BDouble& bdouble);
```

Parameter	Description
bdouble	The BDouble that will be converted into AnyData.

**setFromBfile()**

Converts a Bfile into AnyData.

**Syntax**

```
void setFromBfile(
    const Bfile& bfile);
```

Parameter	Description
bfile	The Bfile that will be converted into AnyData.

**setFromBFloat()**

Converts a BFloat into AnyData.

**Syntax**

```
void setFromBFloat(
    const BFloat& bfloat);
```

Parameter	Description
bfloat	The BFloat that will be converted into AnyData.

## setFromBytes()

Converts a Bytes into AnyData.

### Syntax

```
void setFromBytes(  
    const Bytes& bytes);
```

Parameter	Description
bytes	The Bytes that will be converted into AnyData.

## setFromDate()

Converts a Date into AnyData.

### Syntax

```
void setFromDate(  
    const Date& date);
```

Parameter	Description
date	The Date that will be converted into AnyData.

## setFromIntervalDS()

Converts an IntervalDS into AnyData.

### Syntax

```
void setFromIntervalDS(  
    const IntervalDS& intervals);
```

Parameter	Description
intervals	The IntervalDS that will be converted into AnyData.

## setFromIntervalYM()

Converts an IntervalYM into AnyData.

### Syntax

```
void setFromIntervalYM(  
    const IntervalYM& intervalym);
```

Parameter	Description
intervalym	The IntervalYM that will be converted into AnyData.



## setFromNumber()

Converts a Number into AnyData.

### Syntax

```
void setFromNumber(
    const Number& num);
```

Parameter	Description
num	The Number that will be converted into AnyData.

## setFromObject()

Converts a PObject into AnyData.

### Syntax

```
void setFromObject(
    const PObject* objptr);
```

Parameter	Description
objptr	The PObject that will be converted into AnyData.

## setFromRef()

Converts a PObject into AnyData.

### Syntax

```
void setFromRef(
    const RefAny& ref
    const string &typeName,
    const string &schema);
```

Parameter	Description
ref	The RefAny that will be converted into AnyData.
typeName	The name of the type.
schema	The name of the schema where the type is defined.

## setFromString()

Converts a namespace string into AnyData.

### Syntax

```
void setFromString(
    string& str);
```

setFromTimestamp()

---

Parameter	Description
str	The namespace string that will be converted into AnyData.

## setFromTimestamp()

Converts a Timestamp into AnyData.

### Syntax

```
void setFromTimestamp(  
    const Timestamp& timestamp);
```

Parameter	Description
timestamp	The Timestamp that will be converted into AnyData.

## setNull()

Sets AnyData object to NULL.

### Syntax

```
void setNull();
```

## BatchSQLException Class

The `BatchSQLException` class provides methods for handling batch processing errors. Because `BatchSQLException` class is derived from the [SQLException Class](#), all `BatchSQLException` instances support all methods of `SQLException`, in addition to the methods summarized in [Table 13–6](#).

**See Also:** "Modifying Rows Iteratively" section in [Example 12](#), "Optimizing Performance of OCCI Applications".

**Table 13–6 Summary of BatchSQLException Methods**

Method	Summary
<a href="#">getException()</a> on page 13-19	Returns the exception.
<a href="#">getFailedRowCount()</a> on page 13-19	Returns the number of rows with failed inserts or updates.
<a href="#">getRowNum()</a> on page 13-19	Returns the number of the row that has an insert or updated error

### getException()

Returns the exception that matches the specified `index`.

#### Syntax

```
SQLException getSQLException (
    unsigned int index) const;
```

Parameter	Description
<code>index</code>	The index into the list of errors returned by the batch process.

### getFailedRowCount()

Returns the number of rows for which the statement insert or update failed.

#### Syntax

```
unsigned int getFailedRowCount( ) const;
```

### getRowNum()

Returns the number of the row with an error, matching the specified `index`.

#### Syntax

```
unsigned int getRowNum(
    unsigned int index) const;
```

Parameter	Description
<code>index</code>	The index into the list of errors returned by the batch process.

## Bfile Class

The `Bfile` class defines the common properties of objects of type `BFILE`. A `BFILE` is a large binary file stored in an operating system file outside of the Oracle database. A `Bfile` object contains a logical pointer to a `BFILE`, not the `BFILE` itself.

Methods of the `Bfile` class enable you to perform specific tasks related to `Bfile` objects.

Methods of the `ResultSet` and `Statement` classes, such as `getBfile()` and `setBfile()`, enable you to access an SQL `BFILE` value.

The only methods valid on a `NULL` `Bfile` object are `setName()`, `isNull()`, and `operator=()`.

A `Bfile` object can be initialized by:

- The `setName()` method. The `BFILE` can then be modified by inserting this `BFILE` into the table and then retrieving it using `SELECT ... FOR UPDATE`. The `write()` method will modify the `BFILE`; however, the modified data will be flushed to the table only when the transaction is committed. Note that an insert is not required.
- Assigning an initialized `Bfile` object to it.

**See Also:** In-depth discussion of LOBs in the introductory chapter of *Oracle Database SecureFiles and Large Objects Developer's Guide*,

**Table 13–7 Summary of Bfile Methods**

Method	Summary
<code>Bfile()</code> on page 13-21	<code>Bfile</code> class constructor.
<code>close()</code> on page 13-21	Closes a previously opened <code>BFILE</code> .
<code>closeStream()</code> on page 13-21	Closes the stream obtained from the <code>BFILE</code> .
<code>fileExists()</code> on page 13-21	Tests whether the <code>BFILE</code> exists.
<code>getDirAlias()</code> on page 13-22	Returns the directory object of the <code>BFILE</code> .
<code>getFileName()</code> on page 13-22	Returns the name of the <code>BFILE</code> .
<code>getStream()</code> on page 13-22	Returns data from the <code>BFILE</code> as a <code>Stream</code> object.
<code>getUStringDirAlias()</code> on page 13-22	Returns a <code>UString</code> containing the directory object associated with the <code>BFILE</code> .
<code>getUStringFileName()</code> on page 13-23	Returns a <code>UString</code> containing the file name associated with the <code>BFILE</code> .
<code>isInitialized()</code> on page 13-23	Tests whether the <code>Bfile</code> object is initialized.
<code>isNull()</code> on page 13-23	Tests whether the <code>Bfile</code> object is atomically <code>NULL</code> .
<code>isOpen()</code> on page 13-23	Tests whether the <code>BFILE</code> is open.
<code>length()</code> on page 13-23	Returns the number of bytes in the <code>BFILE</code> .
<code>open()</code> on page 13-24	Opens the <code>BFILE</code> with read-only access.
<code>operator=()</code> on page 13-24	Assigns a <code>BFILE</code> locator to the <code>Bfile</code> object.
<code>operator==(())</code> on page 13-24	Tests whether two <code>Bfile</code> objects are equal.
<code>operator!=(())</code> on page 13-24	Tests whether two <code>Bfile</code> objects are not equal.

**Table 13-7 (Cont.) Summary of Bfile Methods**

Method	Summary
<a href="#">operator==( )</a> on page 13-24	Reads a specified portion of the BFILE into a buffer.
<a href="#">setName( )</a> on page 13-25	Sets the directory object and file name of the BFILE.
<a href="#">setNull( )</a> on page 13-25	Sets the Bfile object to atomically NULL.

## Bfile()

Bfile class constructor.

Syntax	Description
<code>Bfile();</code>	Creates a NULL Bfile object.
<code>Bfile(     const Connection *connectionp);</code>	Creates an uninitialized Bfile object.
<code>Bfile(     const Bfile &amp;srcBfile);</code>	Creates a copy of a Bfile object.

Parameter	Description
<code>connectionp</code>	The connection pointer
<code>srcBfile</code>	The source Bfile object

## close()

Closes a previously opened Bfile.

### Syntax

```
void close();
```

## closeStream()

Closes the stream obtained from the Bfile.

### Syntax

```
void closeStream(  
    Stream *stream);
```

Parameter	Description
<code>stream</code>	The stream to be closed.

## fileExists()

Tests whether the BFILE exists. If the BFILE exists, then TRUE is returned; otherwise, FALSE is returned.

**Syntax**

```
bool fileExists() const;
```

**getDirAlias()**

Returns a string containing the directory object associated with the `BFILE`.

**Syntax**

```
string getDirAlias() const;
```

**getFileName()**

Returns a string containing the file name associated with the `BFILE`.

**Syntax**

```
string getFileName() const;
```

**getStream()**

Returns a `Stream` object read from the `BFILE`. If a stream is already open, it is disallowed to open another stream on the `Bfile` object. The stream must be closed before performing any `Bfile` object operations.

**Syntax**

```
Stream* getStream(  
    unsigned int offset = 1,  
    unsigned int amount = 0);
```

Parameter	Description
<code>offset</code>	The starting position at which to begin reading data from the <code>BFILE</code> . If <code>offset</code> is not specified, the data is written from the beginning of the <code>BLOB</code> . Valid values are numbers greater than or equal to 1.
<code>amount</code>	The total number of bytes to be read from the <code>BFILE</code> ; if <code>amount</code> is 0, the data will be read in a streamed mode from input <code>offset</code> until the end of the <code>BFILE</code> .

**getUStringDirAlias()**

Returns a `UString` containing the directory object associated with the `BFILE`.

---

---

**Note:** The `UString` object is in UTF16 character set. The environment associated with `BFILE` should be associated with UTF16 character set.

---

---

**Syntax**

```
UString getUStringDirAlias() const;
```

## getUStringFileName()

Returns a `UString` containing the file name associated with the `BFILE`.

---

---

**Note:** The `UString` object is in UTF16 character set. The environment associated with `BFILE` should be associated with UTF16 character set.

---

---

### Syntax

```
UString getUStringFileName() const;
```

## isInitialized()

Tests whether the `Bfile` object has been initialized. If the `Bfile` object has been initialized, then `TRUE` is returned; otherwise, `FALSE` is returned.

### Syntax

```
bool isInitialized() const;
```

## isNull()

Tests whether the `Bfile` object is atomically `NULL`. If the `Bfile` object is atomically `NULL`, then `TRUE` is returned; otherwise, `FALSE` is returned.

### Syntax

```
bool isNull() const;
```

## isOpen()

Tests whether the `BFILE` is open. The `BFILE` is considered to be open only if it was opened by a call on this `Bfile` object. (A different `Bfile` object could have opened this file as more than one open can be performed on the same file by associating the file with different `Bfile` objects). If the `BFILE` is open, then `TRUE` is returned; otherwise, `FALSE` is returned.

### Syntax

```
bool isOpen() const;
```

## length()

Returns the number of bytes (inclusive of the end of file marker) in the `BFILE`.

### Syntax

```
unsigned int length() const;
```

## open()

Opens an existing `BFILE` for read-only access. This function is meaningful the first time it is called for a `Bfile` object.

### Syntax

```
void open();
```

## operator=()

Assigns a `Bfile` object to the current `Bfile` object. The source `Bfile` object is assigned to this `Bfile` object only when this `Bfile` object gets stored in the database.

### Syntax

```
Bfile& operator=(
    const Bfile &srcBfile);
```

Parameter	Description
<code>srcBfile</code>	The <code>Bfile</code> object to be assigned to the current <code>Bfile</code> object.

## operator==(())

Compares two `Bfile` objects for equality. The `Bfile` objects are equal if they both refer to the same `BFILE`. If the `Bfile` objects are `NULL`, then `FALSE` is returned. If the `Bfile` objects are equal, then `TRUE` is returned; otherwise, `FALSE` is returned.

### Syntax

```
bool operator==(
    const Bfile &srcBfile) const;
```

Parameter	Description
<code>srcBfile</code>	The <code>Bfile</code> object to be compared with the current <code>Bfile</code> object.

## operator!=(())

Compares two `Bfile` objects for inequality. The `Bfile` objects are equal if they both refer to the same `BFILE`. If the `Bfile` objects are not equal, then `TRUE` is returned; otherwise, `FALSE` is returned.

### Syntax

```
bool operator!=(
    const Bfile &srcBfile) const;
```

Parameter	Description
<code>srcBfile</code>	The <code>Bfile</code> object to be compared with the current <code>Bfile</code> object.



## read()

Reads a part or all of the `BFILE` into the buffer specified, and returns the number of bytes read.

### Syntax

```
unsigned int read(
    unsigned int amt,
    unsigned char *buffer,
    unsigned int bufsize,
    unsigned int offset = 1) const;
```

Parameter	Description
<code>amt</code>	The number of bytes to be read. Valid values are numbers greater than or equal to 1.
<code>buffer</code>	The buffer that the <code>BFILE</code> data is to be read into. Valid values are numbers greater than or equal to <code>amt</code> .
<code>bufsize</code>	The size of the buffer that the <code>BFILE</code> data is to be read into. Valid values are numbers greater than or equal to <code>amt</code> .
<code>offset</code>	The starting position at which to begin reading data from the <code>BFILE</code> . If <code>offset</code> is not specified, the data is written from the beginning of the <code>BFILE</code> .

## setName()

Sets the directory object and file name of the `BFILE`.

Syntax	Description
<pre>void setName(     const string &amp;dirAlias,     const string &amp;fileName);</pre>	Sets the directory object and file name of the <code>BFILE</code> .
<pre>void setName(     const UString &amp;dirAlias,     const UString &amp;fileName);</pre>	Sets the directory object and file name of the <code>BFILE</code> (Unicode support). The client Environment should be initialized in OCCIUTF16 mode.

Parameter	Description
<code>dirAlias</code>	The directory object to be associated with the <code>BFILE</code> .
<code>fileName</code>	The file name to be associated with the <code>BFILE</code> .

## setNull()

Sets the `Bfile` object to atomically `NULL`.

### Syntax

```
void setNull();
```

## Blob Class

The `Blob` class defines the common properties of objects of type `BLOB`. A `BLOB` is a large binary object stored as a column value in a row of a database table. A `Blob` object contains a logical pointer to a `BLOB`, not the `BLOB` itself.

Methods of the `Blob` class enable you to perform specific tasks related to `Blob` objects.

Methods of the `ResultSet` and `Statement` classes, such as `getBlob()` and `setBlob()`, enable you to access an SQL `BLOB` value.

The only methods valid on a `NULL Blob` object are `setName()`, `isNull()`, and `operator=()`.

An uninitialized `Blob` object can be initialized by:

- The `setEmpty()` method. The `BLOB` can then be modified by inserting this `BLOB` into the table and then retrieving it using `SELECT ... FOR UPDATE`. The `write()` method will modify the `BLOB`; however, the modified data will be flushed to the table only when the transaction is committed. Note that an update is not required.
- Assigning an initialized `Blob` object to it.

### See Also:

- In-depth discussion of LOBs in the introductory chapter of *Oracle Database SecureFiles and Large Objects Developer's Guide*,

**Table 13–8 Summary of Blob Methods**

Method	Summary
<code>Blob()</code> on page 13-27	<code>Blob</code> class constructor.
<code>append()</code> on page 13-27	Appends a specified <code>BLOB</code> to the end of the current <code>BLOB</code> .
<code>close()</code> on page 13-27	Closes a previously opened <code>BLOB</code> .
<code>closeStream()</code> on page 13-28	Closes the <code>Stream</code> object obtained from the <code>BLOB</code> .
<code>copy()</code> on page 13-28	Copies a specified portion of a <code>BFILE</code> or <code>BLOB</code> into the current <code>BLOB</code> .
<code>getChunkSize()</code> on page 13-28	Returns the smallest data size to perform efficient writes to the <code>BLOB</code> .
<code>getOptions()</code> on page 13-29	Returns the <code>BLOB</code> 's <code>LobOptionValue</code> for a specified <code>LobOptionType</code> .
<code>getStream()</code> on page 13-29	Returns data from the <code>BLOB</code> as a <code>Stream</code> object.
<code>isInitialized()</code> on page 13-29	Tests whether the <code>Blob</code> object is initialized
<code>isNull()</code> on page 13-29	Tests whether the <code>Blob</code> object is atomically <code>NULL</code> .
<code>isOpen()</code> on page 13-30	Tests whether the <code>BLOB</code> is open.
<code>length()</code> on page 13-30	Returns the number of bytes in the <code>BLOB</code> .
<code>open()</code> on page 13-30	Opens the <code>BLOB</code> with <code>read</code> or <code>read/write</code> access.
<code>operator=()</code> on page 13-30	Assigns a <code>BLOB</code> locator to the <code>Blob</code> object.
<code>operator==( )</code> on page 13-31	Tests whether two <code>Blob</code> objects are equal.
<code>operator!= ( )</code> on page 13-31	Tests whether two <code>Blob</code> objects are not equal.

**Table 13–8 (Cont.) Summary of Blob Methods**

Method	Summary
<a href="#">read()</a> on page 13-31	Reads a portion of the BLOB into a buffer.
<a href="#">setEmpty()</a> on page 13-32	Sets the Blob object to empty.
<a href="#">setNull()</a> on page 13-32	Sets the Blob object to atomically NULL.
<a href="#">setOptions()</a> on page 13-32	Specifies a <code>LobOptionValue</code> for a particular <code>LobOptionType</code> . Enables advanced compression, encryption and deduplication of BLOBs.
<a href="#">trim()</a> on page 13-32	Truncates the BLOB to a specified length.
<a href="#">write()</a> on page 13-33	Writes a buffer into an <i>unopened</i> BLOB.
<a href="#">writeChunk()</a> on page 13-33	Writes a buffer into an <i>open</i> BLOB.

## Blob()

Blob class constructor.

Syntax	Description
<code>Blob();</code>	Creates a NULL Blob object.
<code>Blob(     const Connection *connectionp);</code>	Creates an uninitialized Blob object.
<code>Blob(     const Blob &amp;srcBlob);</code>	Creates a copy of a Blob object.

Parameter	Description
<code>connectionp</code>	The connection pointer
<code>srcBlob</code>	The source Blob object.

## append()

Appends a BLOB to the end of the current BLOB.

### Syntax

```
void append(  
    const Blob &srcBlob);
```

Parameter	Description
<code>srcBlob</code>	The BLOB object to be appended to the current BLOB object.

## close()

Closes a BLOB.

**Syntax**

```
void close();
```

**closeStream()**

Closes the Stream object obtained from the BLOB.

**Syntax**

```
void closeStream(  
    Stream *stream);
```

Parameter	Description
stream	The Stream to be closed.

**copy()**

Copies a part or all of a BFILE or BLOB into the current BLOB.

Syntax	Description
<pre>void copy(     const Bfile &amp;srcBfile,     unsigned int numBytes,     unsigned int dstOffset = 1,     unsigned int srcOffset = 1);</pre>	Copies a part of a BFILE into the current BLOB.
<pre>void copy(     const Blob &amp;srcBlob,     unsigned int numBytes,     unsigned int dstOffset = 1,     unsigned int srcOffset = 1);</pre>	Copies a part of a BLOB into the current BLOB. If the destination BLOB has deduplication enabled, and the source and destination BLOBs are in the same column, the new BLOB will be created as copy-on-write. All other settings are inherited from the source BLOB. If the destination BLOB has deduplication disabled, it will be a completely new copy of the BLOB.

Parameter	Description
srcBfile	The BFILE from which the data is to be copied.
srcBlob	The BLOB from which the data is to be copied.
numBytes	The number of bytes to be copied from the source BFILE or BLOB. Valid values are numbers greater than 0.
dstOffset	The starting position at which to begin writing data into the current BLOB. Valid values are numbers greater than or equal to 1.
srcOffset	The starting position at which to begin reading data from the source BFILE or BLOB. Valid values are numbers greater than or equal to 1.

**getChunkSize()**

Returns the smallest data size to perform efficient writes to the BLOB.

**Syntax**

```
unsigned int getChunkSize() const;
```

**getOptions()**

Returns the BLOB's `LobOptionValue` for a specified `LobOptionType`.

Will throw an exception if attempting to retrieve a value for an option that is not configured on the database column or partition that stores the BLOB.

**Syntax**

```
LobOptionValue getOptions(
    LobOptionType optType);
```

Parameter	Description
<code>optType</code>	The <code>LobOptionType</code> setting requested. These may be combined using bitwise or ( <code> </code> ) to avoid server round trips. See <a href="#">Table 7-1, "Values of Type LobOptionType"</a> and <a href="#">Table 7-2, "Values of Type LobOptionValue"</a>

**getStream()**

Returns a `Stream` object from the BLOB. If a stream is already open, it is disallowed to open another stream on `Blob` object, so the user must always close the stream before performing any `Blob` object operations.

**Syntax**

```
Stream* getStream(
    unsigned int offset = 1,
    unsigned int amount = 0);
```

Parameter	Description
<code>offset</code>	The starting position at which to begin reading data from the BLOB. If <code>offset</code> is not specified, the data is written from the beginning of the BLOB. Valid values are numbers greater than or equal to 1.
<code>amount</code>	The total number of bytes to be read from the BLOB; if <code>amount</code> is 0, the data will be read in a streamed mode from input <code>offset</code> until the end of the BLOB.

**isInitialized()**

Tests whether the `Blob` object is initialized. If the `Blob` object is initialized, then `TRUE` is returned; otherwise, `FALSE` is returned.

**Syntax**

```
bool isInitialized() const;
```

**isNull()**

Tests whether the `Blob` object is atomically `NULL`. If the `Blob` object is atomically `NULL`, then `TRUE` is returned; otherwise, `FALSE` is returned.

**Syntax**

```
bool isNull() const;
```

**isOpen()**

Tests whether the BLOB is open. If the BLOB is open, then TRUE is returned; otherwise, FALSE is returned.

**Syntax**

```
bool isOpen() const;
```

**length()**

Returns the number of bytes in the BLOB.

**Syntax**

```
unsigned int length() const;
```

**open()**

Opens the BLOB in read/write or read-only mode.

**Syntax**

```
void open(
    LobOpenMode mode = OCCI_LOB_READWRITE);
```

Parameter	Description
mode	The mode the BLOB is to be opened in. Valid values are: <ul style="list-style-type: none"> <li>▪ OCCI_LOB_READWRITE</li> <li>▪ OCCI_LOB_READONLY</li> </ul>

**operator=()**

Assigns a BLOB to the current BLOB. The source BLOB gets copied to the destination BLOB only when the destination BLOB gets stored in the table.

**Syntax**

```
Blob& operator=(
    const Blob &srcBlob);
```

Parameter	Description
srcBlob	The source BLOB from which to copy data.

## operator==( )

Compares two `Blob` objects for equality. Two `Blob` objects are equal if they both refer to the same BLOB. Two `NULL` `Blob` objects are not considered equal. If the `Blob` objects are equal, then `TRUE` is returned; otherwise, `FALSE` is returned.

### Syntax

```
bool operator==(
    const Blob &srcBlob) const;
```

Parameter	Description
<code>srcBlob</code>	The source BLOB to be compared with the current BLOB.

## operator!=( )

Compares two `Blob` objects for inequality. Two `Blob` objects are equal if they both refer to the same BLOB. Two `NULL` `Blob` objects are not considered equal. If the `Blob` objects are not equal, then `TRUE` is returned; otherwise, `FALSE` is returned.

### Syntax

```
bool operator!=(
    const Blob &srcBlob) const;
```

Parameter	Description
<code>srcBlob</code>	The source BLOB to be compared with the current BLOB.

## read()

Reads a part or all of the BLOB into a buffer. The actual number of bytes read is returned.

### Syntax

```
unsigned int read(
    unsigned int amt,
    unsigned char *buffer,
    unsigned int bufsize,
    unsigned int offset = 1) const;
```

Parameter	Description
<code>amt</code>	The number of bytes to be read. Valid values are numbers greater than or equal to 1.
<code>buffer</code>	The buffer that the BLOB data is to be read into. Valid values are numbers greater than or equal to <code>amt</code> .
<code>bufsize</code>	The size of the buffer that the BLOB data is to be read into. Valid values are numbers greater than or equal to <code>amt</code> .
<code>offset</code>	The starting position at which to begin reading data from the BLOB. If <code>offset</code> is not specified, the data is written from the beginning of the BLOB.

## setEmpty()

Sets the Blob object to empty.

Syntax	Description
<code>void setEmpty();</code>	Sets the Blob object to empty.
<code>void setEmpty(     const Connection* connectionp);</code>	Sets the Blob object to empty and initializes the connection pointer to the passed parameter.

Parameter	Description
<code>connectionp</code>	The new connection pointer for the BLOB object.

## setNull()

Sets the Blob object to atomically NULL.

### Syntax

```
void setNull();
```

## setOptions()

Specifies a `LobOptionValue` for a particular `LobOptionType`. Enables advanced compression, encryption and deduplication of BLOBs. See [Table 7-1, "Values of Type LobOptionType"](#) and [Table 7-2, "Values of Type LobOptionValue"](#).

Will throw an exception if attempting to set or un-set an option that is not configured on the database column or partition that stores the BLOB. Will throw an exception if attempting to turn off encryption in an encrypted BLOB column.

### Syntax

```
void setOptions(  
    LobOptionType optType,  
    LobOptionValue optValue);
```

Parameter	Description
<code>optType</code>	The <code>LobOptionType</code> setting being specified. These may be combined using bitwise or ( <code> </code> ) to avoid server round trips.
<code>optValue</code>	The <code>LobOptionValue</code> setting for the <code>LobOptionType</code> specified by the <code>optType</code> parameter

## trim()

Truncates the BLOB to the new length specified.

### Syntax

```
void trim(  
    int newLength);
```



```
unsigned int newlen);
```

Parameter	Description
<code>newlen</code>	The new length of the BLOB. Valid values are numbers less than or equal to the current length of the BLOB.

## write()

Writes data from a buffer into a BLOB. This method implicitly opens the BLOB, copies the buffer into the BLOB, and implicitly closes the BLOB. If the BLOB is already open, use [writeChunk\(\)](#) instead. The actual number of bytes written is returned.

### Syntax

```
unsigned int write(
    unsigned int amt,
    unsigned char *buffer,
    unsigned int bufsize,
    unsigned int offset = 1);
```

Parameter	Description
<code>amt</code>	The number of bytes to be written to the BLOB.
<code>buffer</code>	The buffer containing the data to be written to the BLOB.
<code>bufsize</code>	The size of the buffer containing the data to be written to the BLOB. Valid values are numbers greater than or equal to <i>amt</i> .
<code>offset</code>	The starting position at which to begin writing data into the BLOB. If <code>offset</code> is not specified, the data is written from the beginning of the BLOB. Valid values are numbers greater than or equal to 1.

## writeChunk()

Writes data from a buffer into a previously opened BLOB. The actual number of bytes written is returned.

### Syntax

```
unsigned int writeChunk(
    unsigned int amount,
    unsigned char *buffer,
    unsigned int bufsize,
    unsigned int offset = 1);
```

Parameter	Description
<code>amt</code>	The number of bytes to be written to the BLOB.
<code>buffer</code>	The buffer containing the data to be written to the BLOB.
<code>bufsize</code>	The size of the buffer containing the data to be written to the BLOB. Valid values are numbers greater than or equal to <i>amt</i> .
<code>offset</code>	The starting position at which to begin writing data into the BLOB. If <code>offset</code> is not specified, the data is written from the beginning of the BLOB. Valid values are numbers greater than or equal to 1.

## Bytes Class

Methods of the `Bytes` class enable you to perform specific tasks related to `Bytes` objects.

**Table 13–9 Summary of Bytes Methods**

Method	Summary
<a href="#">Bytes()</a> on page 13-34	<code>Bytes</code> class constructor.
<a href="#">byteAt()</a> on page 13-34	Returns the byte at the specified position of the <code>Bytes</code> object.
<a href="#">getBytes()</a> on page 13-35	Returns a byte array from the <code>Bytes</code> object.
<a href="#">isNull()</a> on page 13-35	Tests whether the <code>Bytes</code> object is <code>NULL</code> .
<a href="#">length()</a> on page 13-35	Returns the number of bytes in the <code>Bytes</code> object.
<a href="#">operator=()</a> on page 13-35	Assignment operator for <code>Bytes</code> class.
<a href="#">setNull()</a> on page 13-36	Sets the <code>Bytes</code> object to <code>NULL</code> .

## Bytes()

`Bytes` class constructor.

Syntax	Description
<code>Bytes(   Environment *env = NULL);</code>	Creates a <code>Bytes</code> object.
<code>Bytes(   unsigned char *value,   unsigned int count   unsigned int offset = 0,   const Environment *env = NULL);</code>	Creates a <code>Bytes</code> object that contains a subarray of bytes from a character array.
<code>Bytes(   const Bytes &amp;e);</code>	Creates a copy of a <code>Bytes</code> object, use the syntax

Parameter	Description
<code>env</code>	Environment
<code>value</code>	Initial value of the new object
<code>count</code>	The size of the subset of the character array that will be copied into the new bytes object
<code>offset</code>	The first position from which to begin copying the character array
<code>e</code>	The source <code>Bytes</code> object.

## byteAt()

Returns the byte at the specified position in the `Bytes` object.

**Syntax**

```
unsigned char byteAt(
    unsigned int index) const;
```

Parameter	Description
index	The position of the byte to be returned from the <code>Bytes</code> object; the first byte of the <code>Bytes</code> object is at 0.

**getBytes()**

Copies bytes from a `Bytes` object into the specified byte array.

**Syntax**

```
void getBytes(
    unsigned char *dst,
    unsigned int count,
    unsigned int srcBegin = 0,
    unsigned int dstBegin = 0) const;
```

Parameter	Description
dst	The destination buffer into which data from the <code>Bytes</code> object is to be written.
count	The number of bytes to copy.
srcBegin	The starting position at which data is to be read from the <code>Bytes</code> object; the position of the first byte in the <code>Bytes</code> object is at 0.
dstBegin	The starting position at which data is to be written in the destination buffer; the position of the first byte in <code>dst</code> is at 0.

**isNull()**

Tests whether the `Bytes` object is atomically `NULL`. If the `Bytes` object is atomically `NULL`, then `TRUE` is returned; otherwise `FALSE` is returned.

**Syntax**

```
bool isNull() const;
```

**length()**

This method returns the length of the `Bytes` object.

**Syntax**

```
unsigned int length() const;
```

**operator=()**

Assignment operator for `Bytes` class.

**Syntax**

```
void operator=(
```

## setNull()

---

```
const Bytes& bytes);
```

Parameter	Description
bytes	The original Bytes.

## setNull()

This method sets the `Bytes` object to atomically `NULL`.

### Syntax

```
void setNull();
```

## Clob Class

The `Clob` class defines the common properties of objects of type `CLOB`. A `Clob` is a large character object stored as a column value in a row of a database table. A `Clob` object contains a logical pointer to a `CLOB`, not the `CLOB` itself.

Methods of the `Clob` class enable you to perform specific tasks related to `Clob` objects, including methods for getting the length of a SQL `CLOB`, for materializing a `CLOB` on the client, and for extracting a part of the `CLOB`.

The only methods valid on a `NULL` `CLOB` object are `setName()`, `isNull()`, and `operator=()`.

Methods in the `ResultSet` and `Statement` classes, such as `getClob()` and `setClob()`, enable you to access an SQL `CLOB` value.

An uninitialized `CLOB` object can be initialized by:

- The `setEmpty()` method. The `CLOB` can then be modified by inserting this `CLOB` into the table and retrieving it using `SELECT ... FOR UPDATE`. The `write()` method will modify the `CLOB`; however, the modified data will be flushed to the table only when the transaction is committed. Note that an `insert` is not required.
- Assigning an initialized `Clob` object to it.

### See Also:

- In-depth discussion of LOBs in the introductory chapter of *Oracle Database SecureFiles and Large Objects Developer's Guide*,

**Table 13–10 Summary of Clob Methods**

Method	Summary
<code>Clob()</code> on page 13-38	<code>Clob</code> class constructor.
<code>append()</code> on page 13-38	Appends a <code>Clob</code> at the end of the current <code>Clob</code> .
<code>close()</code> on page 13-39	Closes a previously opened <code>Clob</code> .
<code>closeStream()</code> on page 13-39	Closes the <code>Stream</code> object obtained from the current <code>Clob</code> .
<code>copy()</code> on page 13-39	Copies all or a portion of a <code>Clob</code> or <code>BFILE</code> into the current <code>Clob</code> .
<code>getCharSetForm()</code> on page 13-40	Returns the character set form of the <code>Clob</code> .
<code>getCharSetId()</code> on page 13-40	Returns the character set ID of the <code>Clob</code> .
<code>getCharSetIdUString()</code> on page 13-40	Retrieves the charset name associated with the <code>Clob</code> ; <code>UString</code> version.
<code>getChunkSize()</code> on page 13-40	Returns the smallest data size to perform efficient writes to the <code>CLOB</code> .
<code>getOptions()</code> on page 13-40	Returns the <code>CLOB</code> 's <code>LobOptionValue</code> for a specified <code>LobOptionType</code> .
<code>getStream()</code> on page 13-41	Returns data from the <code>CLOB</code> as a <code>Stream</code> object.
<code>isInitialized()</code> on page 13-41	Tests whether the <code>Clob</code> object is initialized.
<code>isNull()</code> on page 13-41	Tests whether the <code>Clob</code> object is atomically <code>NULL</code> .
<code>isOpen()</code> on page 13-41	Tests whether the <code>Clob</code> is open.

**Table 13–10 (Cont.) Summary of Clob Methods**

Method	Summary
<a href="#">length()</a> on page 13-42	Returns the number of characters in the current CLOB.
<a href="#">open()</a> on page 13-42	Opens the CLOB with read or read/write access.
<a href="#">operator=()</a> on page 13-42	Assigns a CLOB locator to the current Clob object.
<a href="#">operator==(())</a> on page 13-42	Tests whether two Clob objects are equal.
<a href="#">operator!=(())</a> on page 13-43	Tests whether two Clob objects are not equal.
<a href="#">read()</a> on page 13-43	Reads a portion of the CLOB into a buffer.
<a href="#">setCharSetId()</a> on page 13-44	Sets the character set ID associated with the Clob.
<a href="#">setCharSetIdUString()</a> on page 13-44	Sets the character set ID associated with the Clob; used when the environment character set is UTF16.
<a href="#">setCharSetForm()</a> on page 13-44	Sets the character set form associated with the Clob.
<a href="#">setEmpty()</a> on page 13-44	Sets the Clob object to empty.
<a href="#">setNull()</a> on page 13-45	Sets the Clob object to atomically NULL.
<a href="#">setOptions()</a> on page 13-45	Specifies a <code>LobOptionValue</code> for a particular <code>LobOptionType</code> . Enables advanced compression, encryption and deduplication of CLOBs.
<a href="#">trim()</a> on page 13-45	Truncates the Clob to a specified length.
<a href="#">write()</a> on page 13-46	Writes a buffer into an <i>unopened</i> CLOB.
<a href="#">writeChunk()</a> on page 13-46	Writes a buffer into an <i>open</i> CLOB.

## Clob()

Clob class constructor.

Syntax	Description
<code>Clob();</code>	Creates a NULL Clob object.
<code>Clob(     const Connection *connectionp);</code>	Creates an uninitialized Clob object.
<code>Clob(     const Clob *srcClob);</code>	Creates a copy of a Clob object.

Parameter	Description
<code>connectionp</code>	Connection pointer
<code>srcClob</code>	The source Clob object

## append()

Appends a CLOB to the end of the current CLOB.

### Syntax

```
void append(  
    const Clob &srcClob);
```

Parameter	Description
srcClob	The CLOB to be appended to the current CLOB.

## close()

Closes a CLOB.

### Syntax

```
void close();
```

## closeStream()

Closes the Stream object obtained from the CLOB.

### Syntax

```
void closeStream(
    Stream *stream);
```

Parameter	Description
stream	The Stream object to be closed.

## copy()

Copies a part or all of a BFILE or CLOB into the current CLOB.

OCCI does not perform any character set conversions when loading data from a Bfile into a Clob; therefore, ensure that the contents of the Bfile are character data in the server's Clob storage character set.

Syntax	Description
<pre>void copy(     const Bfile &amp;srcBfile,     unsigned int numBytes,     unsigned int dstOffset = 1,     unsigned int srcOffset = 1);</pre>	Copies a BFILE into the current CLOB.
<pre>void copy(     const Clob &amp;srcClob,     unsigned int numBytes,     unsigned int dstOffset = 1,     unsigned int srcOffset = 1);</pre>	<p>Copies a CLOB into the current CLOB.</p> <p>If the destination CLOB has deduplication enabled, and the source and destination CLOBs are in the same column, the new CLOB will be created as copy-on-write. All other settings are inherited from the source CLOB. If the destination CLOB has deduplication disabled, it will be a completely new copy of the CLOB.</p>

Parameter	Description
srcBfile	The BFILE from which the data is to be copied.
srcClob	The CLOB from which the data is to be copied.

Parameter	Description
numBytes	The number of bytes to be copied from the source BFILE or CLOB. Valid values are numbers greater than 0.
dstOffset	The starting position at which data is to be is at 0. The starting position at which to begin writing data into the current CLOB Valid values are numbers greater than or equal to 1 written in the destination buffer; the position of the first byte.
srcOffset	The starting position at which to begin reading data from the source BFILE or CLOB. Valid values are numbers greater than or equal to 1.

## getCharSetForm()

Returns the character set form of the CLOB.

### Syntax

```
CharSetForm getCharSetForm() const;
```

## getCharSetId()

Returns the character set ID of the CLOB, in string form.

### Syntax

```
string getCharSetId() const;
```

## getCharSetIdUString()

Retrieves the charset name associated with the Clob; UString version.

### Syntax

```
UString getCharSetIdUString() const;
```

## getChunkSize()

Returns the smallest data size to perform efficient writes to the CLOB.

### Syntax

```
unsigned int getChunkSize() const;
```

## getOptions()

Returns the CLOB's LobOptionValue for a specified LobOptionType.

Will throw an exception if attempting to retrieve a value for an option that is not configured on the database column or partition that stores the CLOB.

### Syntax

```
LobOptionValue getOptions(  
    LobOptionType optType);
```



Parameter	Description
<code>optType</code>	The <code>LobOptionType</code> setting requested. These may be combined using bitwise or ( <code> </code> ) to avoid server round trips. See <a href="#">Table 7-1, "Values of Type LobOptionType"</a> and <a href="#">Table 7-2, "Values of Type LobOptionValue"</a>

## getStream()

Returns a `Stream` object from the CLOB. If a stream is already open, it is disallowed to open another stream on CLOB object, so the user must always close the stream before performing any `Clob` object operations. The client's character set id and form will be used by default, unless they are explicitly set through [setCharSetId\(\)](#) and [setEmpty\(\)](#) calls.

### Syntax

```
Stream* getStream(
    unsigned int offset = 1,
    unsigned int amount = 0);
```

Parameter	Description
<code>offset</code>	The starting position at which to begin reading data from the CLOB. If <code>offset</code> is not specified, the data is written from the beginning of the CLOB. Valid values are numbers greater than or equal to 1.
<code>amount</code>	The total number of consecutive characters to be read. If <code>amount</code> is 0, the data will be read from the <code>offset</code> value until the end of the CLOB.

## isInitialized()

Tests whether the `Clob` object is initialized. If the `Clob` object is initialized, `TRUE` is returned; otherwise, `FALSE` is returned.

### Syntax

```
bool isInitialized() const;
```

## isNull()

Tests whether the `Clob` object is atomically `NULL`. If the `Clob` object is atomically `NULL`, `TRUE` is returned; otherwise, `FALSE` is returned.

### Syntax

```
bool isNull() const;
```

## isOpen()

Tests whether the CLOB is open. If the CLOB is open, `TRUE` is returned; otherwise, `FALSE` is returned.

### Syntax

```
bool isOpen() const;
```

length()

---

## length()

Returns the number of characters in the CLOB.

### Syntax

```
unsigned int length() const;
```

## open()

Opens the CLOB in `read/write` or `read-only` mode.

### Syntax

```
void open(  
    LObOpenMode mode = OCCI_LOB_READWRITE);
```

Parameter	Description
mode	The mode the CLOB is to be opened in. Valid values are: <ul style="list-style-type: none"><li>▪ <code>OCCI_LOB_READWRITE</code></li><li>▪ <code>OCCI_LOB_READONLY</code></li></ul>

## operator=()

Assigns a CLOB to the current CLOB. The source CLOB gets copied to the destination CLOB only when the destination CLOB gets stored in the table.

### Syntax

```
Clob& operator=(  
    const Clob &srcClob);
```

Parameter	Description
srcClob	The Clob from which the data must be copied.

## operator==( )

Compares two Clob objects for equality. Two Clob objects are equal if they both refer to the same CLOB. Two NULL Clob objects are not considered equal. If the Clob objects are equal, then `TRUE` is returned; otherwise, `FALSE` is returned.

### Syntax

```
bool operator==(  
    const Clob &srcClob) const;
```

Parameter	Description
srcClob	The Clob object to be compared with the current Clob object.

## operator!=()

Compares two `Clob` objects for inequality. Two `Clob` objects are equal if they both refer to the same CLOB. Two `NULL` `Clob` objects are not considered equal. If the `Clob` objects are not equal, then `TRUE` is returned; otherwise, `FALSE` is returned.

### Syntax

```
bool operator!=(
    const Clob &srcClob) const;
```

Parameter	Description
<code>srcClob</code>	The <code>Clob</code> object to be compared with the current <code>Clob</code> object.

## read()

Reads a part or all of the CLOB into a buffer.

Returns the actual number of characters read for fixed-width character sets, such as UTF16, or the number of bytes read for multibyte character sets, including UTF8.

The client's character set id and form will be used by default, unless they are explicitly set through [setCharSetId\(\)](#), [setCharSetIdUString\(\)](#) and [setCharSetForm\(\)](#) calls.

Syntax	Description
<pre>unsigned int read(     unsigned int amt,     unsigned char *buffer,     unsigned int bufsize,     unsigned int offset=1) const;</pre>	Reads a part or all of the CLOB into a buffer.
<pre>unsigned int read(     unsigned int amt,     unsigned utext *buffer,     unsigned int bufsize,     unsigned int offset=1) const;</pre>	Reads a part or all of the CLOB into a buffer; globalization enabled. Should be called after setting character set to OCCIUTF16 using <a href="#">setCharSetId()</a> method.

---

**Note:** For the second version of the method, the return value represents either the number of characters read for fixed-width character sets (UTF16), or the number of bytes read for multibyte character sets (including UTF8).

---

Parameter	Description
<code>amt</code>	The number of bytes to be read. from the CLOB.
<code>buffer</code>	The buffer that the CLOB data is to be read into.
<code>bufsize</code>	The size of the buffer. Valid values are numbers greater than or equal to <code>amt</code> .
<code>offset</code>	The starting position at which to begin reading data from the CLOB. If <code>offset</code> is not specified, the data is written from the beginning of the CLOB. Valid values are numbers greater than or equal to 1.

## setCharSetId()

Sets the Character set Id associated with Clob. The character set id set will be used for read/write and [getStream\(\)](#) operations. If no value is set explicitly, the default client's character set id is used. List of character sets supported is given in Globalization Support Guide Appendix A.

### Syntax

```
void setCharSetId(
    const string &charset);
```

Parameter	Description
charset	Oracle supported character set name, such as E8DEC, ZHT16BIG5, or OCCIUTF16.

## setCharSetIdUString()

Sets the Character set Id associated with Clob; used when the environment's character set is UTF16. The charset id set will be used for read, write and [getStream\(\)](#) operations.

### Syntax

```
void setCharSetIdUString(
    const string &charset);
```

Parameter	Description
charset	Oracle supported character set name, such as WE8DEC, ZHT16BIG5, or OCCIUTF16 in UString (UTF16 character set).

## setCharSetForm()

Sets the character set form associated with the CLOB. The charset form set will be used for read, write and [getStream\(\)](#) operations. If no value is set explicitly, by default, OCCI\_SQLCS\_IMPLICIT will be used.

### Syntax

```
void setCharSetForm(
    CharSetForm csfrm );
```

Parameter	Description
csfrm	The charset form for Clob.

## setEmpty()

Sets the Clob object to empty.

Syntax	Description
<code>void setEmpty();</code>	Sets the Clob object to empty.
<code>void setEmpty(     const Connection* connectionp);</code>	Sets the Clob object to empty and initializes the connection pointer to the passed parameter.

Parameter	Description
<code>connectionp</code>	The new connection pointer for the Clob object.

## setNull()

Sets the Clob object to atomically NULL.

### Syntax

```
void setNull();
```

## setOptions()

Specifies a `LobOptionValue` for a particular `LobOptionType`. Enables advanced compression, encryption and deduplication of CLOBs. See [Table 7-1, "Values of Type LobOptionType"](#) and [Table 7-2, "Values of Type LobOptionValue"](#).

Will throw an exception if attempting to set or un-set an option that is not configured on the database column or partition that stores the CLOB. Will throw an exception if attempting to turn off encryption in an encrypted CLOB column.

### Syntax

```
void setOptions(  
    LobOptionType optType,  
    LobOptionValue optValue);
```

Parameter	Description
<code>optType</code>	The <code>LobOptionType</code> setting being specified. These may be combined using bitwise or ( <code> </code> ) to avoid server round trips.
<code>optValue</code>	The <code>LobOptionValue</code> setting for the <code>LobOptionType</code> specified by the <code>optType</code> parameter

## trim()

Truncates the CLOB to the new length specified.

### Syntax

```
void trim(  
    unsigned int newlen);
```

Parameter	Description
<code>newlen</code>	The new length of the CLOB. Valid values are numbers less than or equal to the current length of the CLOB.

## write()

Writes data from a buffer into a CLOB.

This method implicitly opens the CLOB, copies the buffer into the CLOB, and implicitly closes the CLOB. If the CLOB is already open, use [writeChunk\(\)](#) instead. The actual number of characters written is returned. The client's character set id and form will be used by default, unless they are explicitly set through [setCharSetId\(\)](#) and [setCharSetForm\(\)](#) calls.

Syntax	Description
<pre>unsigned int write(     unsigned int amt,     unsigned char *buffer,     unsigned int bufsize,     unsigned int offset=1);</pre>	Writes data from a buffer into a CLOB.
<pre>unsigned int write(     unsigned int amt,     utext *buffer,     unsigned int bufsize,     unsigned int offset=1);</pre>	Writes data from a UTF16 buffer into a CLOB; globalization enabled. Should be called after setting character set to OCCIUTF16 using <a href="#">setCharSetIdUString()</a> method.

Parameter	Description
amt	The amount parameter represents: <ul style="list-style-type: none"> <li>number of characters written for fixed-width charactersets (UTF16)</li> <li>number of bytes written for multibyte charactersets (including UTF8)</li> </ul>
buffer	The buffer containing the data to be written to the CLOB.
bufsize	The size of the buffer containing the data to be written to the CLOB. Valid values are numbers greater than or equal to amt.
offset	The starting position at which to begin writing data into the CLOB. If <code>offset</code> is not specified, the data is written from the beginning of the CLOB. Valid values are numbers greater than or equal to 1.

## writeChunk()

Writes data from a buffer into a previously opened CLOB.

The actual number of characters written is returned. The client's character set id and form will be used by default, unless they are explicitly set through [setCharSetId\(\)](#) and [setCharSetForm\(\)](#) calls.

Syntax	Description
<pre>unsigned int writeChunk(     unsigned int amt,     unsigned char *buffer,     unsigned int bufsize,     unsigned int offset=1);</pre>	Writes data from a buffer into a previously opened CLOB.

---

Syntax	Description
<pre>unsigned int writeChunk(     unsigned int amt,     utext *buffer,     unsigned int bufsize,     unsigned int offset=1);</pre>	Writes data from a UTF16 buffer into a CLOB; globalization enabled. Should be called after setting <code>characterSet</code> to <code>OCCIUTF16</code> using <code>setCharSetIdUString()</code> method.

---

---

Parameter	Description
<code>amt</code>	The amount parameter represents <ul style="list-style-type: none"><li>number of characters written for fixed-width character sets (UTF16)</li><li>number of bytes written for multibyte character sets (including UTF8)</li></ul>
<code>buffer</code>	The buffer containing the data to be written to the CLOB.
<code>bufsize</code>	The size of the buffer containing the data to be written to the CLOB. Valid values are numbers greater than or equal to <code>amt</code> .
<code>offset</code>	The starting position at which to begin writing data into the CLOB. If <code>offset</code> is not specified, the data is written from the beginning of the CLOB. Valid values are numbers greater than or equal to 1.

---

## Connection Class

The Connection class represents a connection with a specific database. Within the context of a connection, SQL statements are executed and results are returned.

**Table 13–11 Enumerated Values Used by Connection Class**

Attribute	Options
FailOverEventType	<ul style="list-style-type: none"> <li>■ FO_BEGIN indicates that a lost connection has been detected; failover is starting.</li> <li>■ FO_END indicates that a failover completed successfully; the Connection is ready for use.</li> <li>■ FO_ABORT indicates that the failover was unsuccessful; it will not be attempted again.</li> <li>■ FO_REAUTH indicates that the user session has been reauthenticated.</li> <li>■ FO_ERROR indicates that a failover was unsuccessful; the application can handle the error and retry failover.</li> </ul>
FailOverType	<ul style="list-style-type: none"> <li>■ FO_NONE indicates that the user requested no protection for failover.</li> <li>■ FO_SESSION indicates that the user requested only session failover.</li> <li>■ FO_SELECT indicates that the use requested select failover.</li> </ul>
ProxyType	<ul style="list-style-type: none"> <li>■ PROXY_DEFAULT is the database user name.</li> </ul>

**Table 13–12 Summary of Connection Methods**

Method	Summary
<a href="#">changePassword()</a> on page 13-49	Changes the password for the current user.
<a href="#">commit()</a> on page 13-50	Commits changes made since the previous commit or rollback and release any database locks held by the session.
<a href="#">createStatement()</a> on page 13-50	Creates a Statement object to execute SQL statements.
<a href="#">flushCache()</a> on page 13-51	Flushes the object cache associated with the connection.
<a href="#">getClientCharSet()</a> on page 13-51	Returns the default client character set.
<a href="#">getClientCharSetUString()</a> on page 13-51	Returns the globalization enabled client character set in UString.
<a href="#">getClientNCHARCharSet()</a> on page 13-51	Returns the default client NCHAR character set.
<a href="#">getClientNCHARCharSetUString()</a> on page 13-51	Returns the globalization enabled client NCHAR character set in UString.
<a href="#">getClientVersion()</a> on page 13-52	Returns the version of the client used.
<a href="#">getMetaData()</a> on page 13-52	Returns the metadata for an object accessible from the connection.
<a href="#">getOCIServer()</a> on page 13-53	Returns the OCI server context associated with the connection.
<a href="#">getOCIServiceContext()</a> on page 13-53	Returns the OCI service context associated with the connection.



**Table 13–12 (Cont.) Summary of Connection Methods**

Method	Summary
<a href="#">getOCISession()</a> on page 13-53	Returns the OCI session context associated with the connection.
<a href="#">getServerVersion()</a> on page 13-53	Returns the version of the Oracle server used, as <code>string</code> .
<a href="#">getServerVersionUString()</a> on page 13-53	Returns the version of the Oracle server used, as a <code>UString</code> .
<a href="#">getStmtCacheSize()</a> on page 13-53	Retrieves the size of the statement cache.
<a href="#">getTag()</a> on page 13-54	Returns the tag associated with the connection.
<a href="#">isCached()</a> on page 13-54	Determines if the specified statement is cached.
<a href="#">pinVectorOfRefs()</a> on page 13-54	Pins an entire vector of <code>Ref</code> objects into object cache in a single round trip; pinned objects are available through an <code>OUT</code> parameter vector.
<a href="#">postToSubscriptions()</a> on page 13-55	Posts notifications to subscriptions.
<a href="#">readVectorOfBfiles()</a> on page 13-55	Reads multiple <code>Bfiles</code> in a single server round-trip.
<a href="#">readVectorOfBlobs()</a> on page 13-56	Reads multiple <code>Blobs</code> in a single server round-trip.
<a href="#">readVectorOfClobs()</a> on page 13-56	Reads multiple <code>Clobs</code> in a single server round-trip.
<a href="#">registerSubscriptions()</a> on page 13-57	Registers several <code>Subscriptions</code> for notification.
<a href="#">rollback()</a> on page 13-57	Rolls back all changes made since the previous commit or rollback and release any database locks held by the session.
<a href="#">setCollectionAccessMode()</a> on page 13-58	Disables or enables caching of collections on demand.
<a href="#">setStmtCacheSize()</a> on page 13-58	Enables or disables statement caching.
<a href="#">setTAFNotify()</a> on page 13-58	Registers failover callback function on the <code>Connection</code> object.
<a href="#">terminateStatement()</a> on page 13-59	Closes a <code>Statement</code> object and free all resources associated with it.
<a href="#">unregisterSubscription()</a> on page 13-59	Unregisters a <code>Subscription</code> , turns off its notifications.
<a href="#">writeVectorOfBlobs()</a> on page 13-60	Writes multiple <code>Blobs</code> in a single server round-trip.
<a href="#">writeVectorOfClobs()</a> on page 13-60	Writes multiple <code>Clobs</code> in a single server round-trip.

## changePassword()

Changes the password of the user currently connected to the database.

Syntax	Description
<pre>void changePassword(     const string &amp;user,     const string &amp;oldPassword,     const string &amp;newPassword)=0;</pre>	Changes the password of the user.

Syntax	Description
<pre>void changePassword(     const UString &amp;user,     const UString &amp;oldPassword,     const UString &amp;newPassword)=0;</pre>	Changes the password of the user (Unicode support). The client Environment should be initialized in OCCIUTF16 mode.

Parameter	Description
user	The user currently connected to the database.
oldPassword	The current password of the user.
newPassword	The new password of the user.

## commit()

Commits all changes made since the previous commit or rollback, and releases any database locks currently held by the session.

### Syntax

```
void commit()=0;
```

## createStatement()

Creates a Statement object with the SQL statement specified.

Syntax	Description
<pre>Statement* createStatement(     const string &amp;sql)=0;</pre>	Searches the cache for a specified SQL statement and returns it; if not found, creates a new statement.
<pre>Statement* createStatement(     const string &amp;sql,     const string &amp;tag)=0;</pre>	Searches the cache for a statement with a matching tag; if not found, creates a new statement with the specified SQL content.
<pre>Statement* createStatement(     const UString &amp;sql)=0;</pre>	Searches the cache for a specified SQL statement and returns it; if not found, creates a new statement. Globalization enabled.
<pre>Statement* createStatement(     const Ustring &amp;sql,     const Ustring &amp;tag)=0;</pre>	Searches the cache for a matching tag and returns it; if not found, creates a new statement with the specified SQL content. Globalization enabled.

Parameter	Description
sql	The SQL string to be associated with the statement object.
tag	The tag whose associated statement needs to be retrieved from the cache. Ignored if statement caching is disabled.

---

---

**Note:**

- For the caching enabled version of this method, the cache is initially searched for a statement with a matching `tag`, which is returned. If no match is found, the cache is searched again for a statement that matches the `sql` parameter, which is returned. If no match is found, a new statement with a `NULL tag` is created and returned. If the `sql` parameter is empty and the `tag` search fails, this call generates an `ERROR`.
  - Non-caching versions of this method always create and return a new statement.
- 
- 

## flushCache()

Flushes the object cache associated with the connection.

**Syntax**

```
void flushCache()=0;
```

## getClientCharSet()

Returns the session's character set.

**Syntax**

```
string getClientCharSet() const=0;
```

## getClientCharSetUString()

Returns the globalization enabled client character set in `UString`.

**Syntax**

```
UString getClientCharSetUString() const=0;
```

## getClientNCHARCharSet()

Returns the session's `NCHAR` character set.

**Syntax**

```
string getClientNCHARCharSet() const=0;
```

## getClientNCHARCharSetUString()

Returns the globalization enabled client `NCHAR` character set in `UString`.

**Syntax**

```
UString getClientNCHARCharSetUString() const=0;
```

## getClientVersion()

Returns the version of the client library the application is using at runtime.

This is used by applications to determine the version of the OCCI client at runtime, and if the application uses several separate code paths that use several different client patchsets.

The values of parameters `majorVersion` and `minorVersion` use macros `OCCI_MAJOR_VERSION` and `OCCI_MINOR_VERSION`, respectively. These macros define the major and minor versions of the OCCI client library. Compares the versions returned.

### Syntax

```
void getClientVersion(
    int &majorVersion,
    int &minorVersion,
    int &updateNum,
    int &patchNumber,
    int &portUpdateNum)
```

Parameter	Description
<code>majorVersion</code>	The major version of the client library.
<code>minorVersion</code>	The minor version of the client library.
<code>updateNum</code>	The update number.
<code>patchNumber</code>	The number of the patch applied to the library.
<code>portUpdateNumber</code>	The number of the port-specific port update applied to the library.

## getMetaData()

Returns metadata for an object in the database.

Syntax	Description
<pre>MetaData getMetaData(     const string &amp;object,     MetaData::ParamType prmtyp=MetaData::PTYPE_UNK) const=0;</pre>	Returns metadata for an object in the database.
<pre>MetaData getMetaData(     const UString &amp;object,     MetaData::ParamType prmtyp=MetaData::PTYPE_UNK) const=0;</pre>	Returns metadata for a globalization enabled object in the database.
<pre>MetaData getMetaData(     const RefAny &amp;ref) const=0;</pre>	Returns metadata for an object in the database through a reference.

Parameter	Description
<code>object</code>	The SQL string to be associated with the statement object.
<code>prmtyp</code>	The type of the schema object being described, as defined by the enumerated <code>ParamType</code> of the <code>MetaData</code> class, <a href="#">Table 13-26</a> on page 13-127

---

Parameter	Description
ref	A REF to the Type Descriptor Object (TDO) of the type to be described.

---

## getOCIServer()

Returns the OCI server context associated with the connection.

### Syntax

```
OCIServer* getOCIServer() const=0;
```

## getOCIServiceContext()

Returns the OCI service context associated with the connection.

### Syntax

```
OCISvcCtx* getOCIServiceContext() const=0;
```

## getOCISession()

Returns the OCI session context associated with the connection.

### Syntax

```
OCISession* getOCISession() const=0;
```

## getServerVersion()

Returns the version of the database server, as a `string`, used by the current `Connection` object. This can be used when an application uses several separate code paths and connects to several different server versions.

### Syntax

```
string getServerVersion() const;
```

## getServerVersionUString()

Returns the version of the database server, as a `UString`, used by the current `Connection` object. This can be used when an application uses several separate code paths and connects to several different server versions.

### Syntax

```
UString getServerVersionUString() const;
```

## getStmtCacheSize()

Retrieves the size of the statement cache.

**Syntax**

```
unsigned int getStmtCacheSize() const=0;
```

**getTag()**

Returns the tag associated with the connection. Valid only for connections from a stateless connection pool.

**Syntax**

```
string getTag() const=0;
```

**isCached()**

Determines if the specified statement is cached.

Syntax	Description
<pre>bool isCached(     const string &amp;sql,     const string &amp;tag="");</pre>	Searches the cache for a statement with a matching tag. If the tag is not specified, the cache is searched for a matching SQL statement.
<pre>bool isCached(     const Ustring &amp;sql,     const Ustring &amp;tag)=0;</pre>	Searches the cache for a statement with a matching tag. If the tag is not specified, the cache is searched for a matching SQL statement. Globalization enabled.

Parameter	Description
sql	The SQL string to be associated with the statement object.
tag	The tag whose associated statement needs to be retrieved from the cache. Ignored if statement caching is disabled.

**pinVectorOfRefs()**

Pins an entire vector of Ref objects into object cache in a single round-trip. Pinned objects are available through an OUT parameter vector.

Syntax	Description
<pre>template &lt;class T&gt; void pinVectorOfRefs(     const Connection *conn,     vector &lt;Ref&lt;T&gt;&gt; &amp; vect,     vector &lt;T*&gt; &amp;vectObj,     LockOptions lockOpt=OCCI_LOCK_NONE);</pre>	Returns the objects.
<pre>template &lt;class T&gt; void pinVectorOfRefs(     const Connection *conn,     vector &lt;Ref&lt;T&gt;&gt; &amp; vect,     LockOptions lockOpt=OCCI_LOCK_NONE);</pre>	Does not explicitly return the objects; an application needs to dereference a particular Ref object by a ptr() call, which returns a previously pinned object.

Parameter	Description
conn	Connection
vect	Vector of Ref objects that will be pinned.
vectObj	Vector that will contain objects after the pinning operation is complete; an OUT parameter.
lockOpt	Lock option used during the pinning of the array, as defined by LockOptions in <a href="#">Table 13-2</a> on page 13-6. The only supported value is OCCI_LOCK_NONE.

## postToSubscriptions()

Posts notifications to subscriptions.

The Subscription object needs to have a valid subscription name, and the namespace should be set to NS\_ANONYMOUS. The payload needs to be set before invoking this call; otherwise, the payload is assumed to be NULL and is not delivered.

The caller has to preserve the payload until the posting call is complete. This call provides a best-effort guarantee; a notification is sent to registered clients at most once.

This call is primarily used for light-weight notification and is useful in the case of several system events. If the application needs more rigid guarantees, it can use the Oracle Streams Advanced Queuing functionality.

### Syntax

```
void postToSubscriptions(
    const vector<aq::Subscription>& sub)=0;
```

Parameter	Description
sub	The vector of subscriptions that receive postings.

## readVectorOfBfiles()

Reads multiple Bfiles in a single server round-trip. All Bfiles must already be open for reading.

### Syntax

```
void readVectorOfBfiles(
    const Connection *conn,
    vector<Bfile> &vec,
    oraub8 *byteAmts,
    oraub8 *offsets,
    unsigned char *buffers[],
    oraub8 *bufferLengths);
```

Parameter	Description
conn	Connection.
vec	Vector of Bfile objects; each Bfile must be open for reading.
byteAmts	Array of amount of bytes to read from the individual Bfiles. The actual number of bytes read from each Bfile is returned in this array.

Parameter	Description
offsets	Array of offsets, starting position where reading from the <code>Bfiles</code> starts.
buffers	Array of pointers to buffers into which the data is read.
bufferLengths	Array of sizes of each buffer, in bytes.

## readVectorOfBlobs()

Reads multiple BLOBs in a single server round-trip.

### Syntax

```
void readVectorOfBlobs(
    const Connection *conn,
    vector<Blob> &vec,
    oraub8 *byteAmts,
    oraub8 *offsets,
    unsigned char *buffers[],
    oraub8 *bufferLengths);
```

Parameter	Description
conn	Connection.
vec	Vector of <code>Blob</code> objects.
byteAmts	Array of amount of bytes to read from the individual <code>Blobs</code> . The actual number of bytes read from each <code>Blob</code> is returned in this array.
offsets	Array of offsets, starting position where reading from the <code>Blobs</code> starts.
buffers	Array of pointers to buffers into which the data is read.
bufferLengths	Array of sizes of each buffer, in bytes.

## readVectorOfClobs()

Reads multiple CLOBs in a single server round-trip. All CLOBs should be in the same character set form and belong to the same character set ID.

Syntax	Description
<pre>void readVectorOfClobs(     const Connection *conn,     vector&lt;Clob&gt; &amp;vec,     oraub8 *byteAmts,     araub8 *charAmts,     oraub8 *offsets,     unsigned char *buffers[],     oraub8 *bufferLengths);</pre>	General form of the method.



Syntax	Description
<pre>void readVectorOfClobs(     const Connection *conn,     vector&lt;Clob&gt; &amp;vec,     oraub8 *byteAmts,     araub8 *charAmts,     oraub8 *offsets,     utext *buffers[],     oraub8 *bufferLengths);</pre>	Form of the method used with <code>utext</code> buffers, when data is in UTF16 character set encoding.

Parameter	Description
<code>conn</code>	Connection.
<code>vec</code>	Vector of <code>Clob</code> objects.
<code>byteAmts</code>	Array of amount of bytes to read from the individual <code>Clob</code> s. Only used if the <code>charAmts</code> is <code>NULL</code> , or 0 for any <code>Clob</code> index. Returns the number of bytes read for each <code>Clob</code> .
<code>charAmts</code>	Array of amount of characters to read from individual <code>Clob</code> s. Returns the number of characters read for each <code>Clob</code> .
<code>offsets</code>	Array of offsets, starting position where reading from the <code>Clob</code> s starts, in characters.
<code>buffers</code>	Array of pointers to buffers into which the data is read.
<code>bufferLengths</code>	Array of sizes of each buffer, in bytes.

## registerSubscriptions()

Registers `Subscriptions` for notification.

New client processes and existing processes that restart after a shut down must register for all subscriptions of interest. If the client stays up during a server shut down and restart, this client will continue to receive notifications for `DISCONNECTED` registrations, but not for `CONNECTED` registrations because they are lost during the server down time.

### Syntax

```
void registerSubscriptions(
    const vector<aq::Subscription>& sub)=0;
```

Parameter	Description
<code>sub</code>	Vector of subscriptions that will be registered for notification.

## rollback()

Drops all changes made since the previous commit or rollback, and releases any database locks currently held by the session.

**Syntax**

```
void rollback()=0;
```

**setCollectionAccessMode()**

Disables or enables caching of collections on demand.

**Syntax**

```
void setCollectionAccessMode(  
    CollectionAccessMode mode);
```

Parameter	Description
mode	The mode of collection access, <code>CollectionAccessMode</code> , defined in <a href="#">Table 13-11</a> , "Enumerated Values Used by Connection Class" on page 13-48.

**setStmtCacheSize()**

Enables or disables statement caching. A nonzero value will enable statement caching, with a cache of specified size. A zero value will disable caching.

**Syntax**

```
void setStmtCacheSize(  
    unsigned int cacheSize)=0;
```

Parameter	Description
cacheSize	The maximum number of statements in the cache.

**setTAFNotify()**

Registers the failover callback function on the `Connection` object for which failover is configured and must be detected.

The failover callback should return `OCCI_SUCCESS` to indicate that OCCI can continue with default processing. The failover event, `foEvent`, is defined in [Table 13-11](#) on page 13-48. When the `foEvent` is `FO_ERROR`, the callback function may return either `FO_RETRY` to indicate that failover must be attempted again, or `OCCI_SUCCESS` to end failover attempts.

**Syntax**

```
void setTAFNotify(  
    int (*notifyFn)(  
        Environment *env,  
        Connection *conn,  
        void *ctx,  
        FailOverType foType,  
        FailOverEventType foEvent),  
    void *ctxTAF)
```

Parameter	Description
notifyFn	The user defined callback function invoked during failover events.
env	Environment object from which the failing Connection was created.
conn	The failing Connection on which the callback function is registered.
ctx	Context supplied by the user when registering the callback.
foType	The configured FailOverType, values FO_SESSION or FO_SELECT, as defined in <a href="#">Table 13–11</a> on page 13-48.
foEvent	Failover event type that is triggering the callback; the FailOverEventType, values FO_BEGIN, FO_END, FO_ABORT and FO_ERROR as defined in <a href="#">Table 13–11</a> on page 13-48.
ctxTAF	User context passed back to the callback function at invocation.

## terminateStatement()

Closes a Statement object.

Syntax	Description
<pre>void terminateStatement(     Statement *stmt)=0;</pre>	Closes a Statement object and frees all resources associated with it.
<pre>void terminateStatement(     Statement *stmt,     const string &amp;tag)=0;</pre>	Releases statement back to the cache after adding an optional tag, a string.
<pre>void terminateStatement(     Statement* stmt,     const UString &amp;tag) = 0;</pre>	Releases statement back to the cache after adding an optional tag, a UString.

Parameter	Description
stmt	The Statement to be closed.
tag	The tag associated with the statement, either a string or a UString.

## unregisterSubscription()

Unregisters a Subscription, turning off its notifications.

### Syntax

```
void unregisterSubscription(
    const aq::Subscription& sub)=0;
```

Parameter	Description
sub	Subscription whose notifications will be turned off.

## writeVectorOfBlobs()

Writes multiple Blobs in a single server round-trip.

### Syntax

```
void writeVectorOfBlobs(
    const Connection *conn,
    vector<Blob> &vec,
    oraub8 *byteAmts,
    oraub8 *offsets,
    unsigned char *buffers[],
    oraub8 *bufferLengths);
```

Parameter	Description
conn	Connection.
vec	Vector of Blob objects.
byteAmts	Array of amount of bytes to write to the individual Blobs.
offsets	Array of offsets, starting position where writing to the Blobs starts.
buffers	Array of pointers to buffers from which the data is written.
bufferLengths	Array of sizes of each buffer, in bytes.

## writeVectorOfClobs()

Writes multiple Clobs in a single server round-trip. All Clobs should be in the same character set form and belong to the same character set ID.

Syntax	Description
<pre>void writeVectorOfClobs(     const Connection *conn,     vector&lt;Clob&gt; &amp;vec,     oraub8 *byteAmts,     araub8 *charAmts,     oraub8 *offsets,     unsigned char *buffers[],     oraub8 *bufferLengths);</pre>	General form of the method.
<pre>void writeVectorOfClobs(     const Connection *conn,     vector&lt;Clob&gt; &amp;vec,     oraub8 *byteAmts,     araub8 *charAmts,     oraub8 *offsets,     utext *buffers[],     oraub8 *bufferLengths);</pre>	Form of the method used with utext buffers, when data is in UTF16 character set encoding.

---

<b>Parameter</b>	<b>Description</b>
conn	Connection.
vec	Vector of Clob objects.
byteAmts	Array of amount of bytes to write to the individual Clobs. Only used if the charAmts is NULL or 0 for any Clob index. Returns the number of bytes written for each Clob.
charAmts	Array of amount of characters to write to individual Clobs. Returns the number of characters read for each Clob.
offsets	Array of offsets, starting position where writing to the Clobs starts, in characters.
buffers	Array of pointers to buffers from which the data is written.
bufferLengths	Array of sizes of each buffer, in bytes.

---

## ConnectionPool Class

The ConnectionPool class represents a pool of connections for a specific database.

**Table 13–13 Summary of ConnectionPool Methods**

Method	Summary
<a href="#">createConnection()</a> on page 13-62	Creates a pooled connection.
<a href="#">createProxyConnection()</a> on page 13-63	Creates a proxy connection.
<a href="#">getBusyConnections()</a> on page 13-63	Returns the number of busy connections in the connection pool.
<a href="#">getIncrConnections()</a> on page 13-64	Returns the number of incremental connections in the connection pool.
<a href="#">getMaxConnections()</a> on page 13-64	Returns the maximum number of connections in the connection pool.
<a href="#">getMinConnections()</a> on page 13-64	Returns the minimum number of connections in the connection pool.
<a href="#">getOpenConnections()</a> on page 13-64	Returns the number of open connections in the connection pool.
<a href="#">getPoolName()</a> on page 13-64	Returns the name of the connection pool.
<a href="#">getStmtCacheSize()</a> on page 13-64	Retrieves the size of the statement cache.
<a href="#">getTimeOut()</a> on page 13-65	Returns the time out period for a connection in the connection pool.
<a href="#">setErrorOnBusy()</a> on page 13-65	Specifies that a <code>SQLException</code> should be generated when all connections in the connection pool are busy and no further connections can be opened.
<a href="#">setPoolSize()</a> on page 13-65	Sets the minimum, maximum, and incremental number of pooled connections for the connection pool.
<a href="#">setStmtCacheSize()</a> on page 13-65	Enables or disables statement caching.
<a href="#">setTimeOut()</a> on page 13-65	Sets the time out period, in seconds, for a connection in the connection pool.
<a href="#">terminateConnection()</a> on page 13-66	Destroys the connection.

### createConnection()

Creates a pooled connection.

Syntax	Description
<pre>Connection* createConnection(     const string &amp;userName,     const string &amp;password)=0;</pre>	Creates a pooled connection.
<pre>Connection* createConnection(     const UString &amp;username,     const UString &amp;password)=0;</pre>	Creates a globalization enabled pooled connection.

Parameter	Description
userName	The name of the user with which to connect.
password	The password of the user.

## createProxyConnection()

Creates a proxy connection from the connection pool.

Syntax	Description
<pre>Connection* createProxyConnection(     const string &amp;name,     Connection::ProxyType         proxyType=Connection::PROXY_DEFAULT)=0;</pre>	Creates a proxy connection.
<pre>Connection* createProxyConnection(     const UString &amp;name,     Connection::ProxyType         proxyType=Connection::PROXY_DEFAULT)=0;</pre>	Creates a globalization enabled proxy connection.
<pre>Connection* createProxyConnection(     const string &amp;name,     string roles[],     int numRoles,     Connection::ProxyType         proxyType=Connection::PROXY_DEFAULT)=0;</pre>	Creates a proxy connection for several roles.
<pre>Connection* createProxyConnection(     const UString &amp;name,     string roles[],     unsigned int numRoles,     Connection::ProxyType         proxyType=Connection::PROXY_DEFAULT)=0;</pre>	Creates a globalization enabled proxy connection for several roles.

Parameter	Description
name	The user name to connect with.
roles	The roles to activate on the database server.
numRoles	The number of roles to activate on the database server.
proxyType	The type of proxy authentication to perform, <code>ProxyType</code> , defined in <a href="#">Table 13-11</a> on page 13-48. Valid values are: <ul style="list-style-type: none"> <li>▪ <code>PROXY_DEFAULT</code> representing a database user name.</li> </ul>

## getBusyConnections()

Returns the number of busy connections in the connection pool. When using database resident connection pooling, this is the number of persistent connections to the Connection Broker.

### Syntax

```
unsigned int getBusyConnections() const=0;
```

## getIncrConnections()

Returns the number of incremental connections in the connection pool. When using database resident connection pooling, this is the number of persistent connections to the Connection Broker.

### Syntax

```
unsigned int getIncrConnections() const=0;
```

## getMaxConnections()

Returns the maximum number of connections in the connection pool. When using database resident connection pooling, this is the number of persistent connections to the Connection Broker.

### Syntax

```
unsigned int getMaxConnections() const=0;
```

## getMinConnections()

Returns the minimum number of connections in the connection pool. When using database resident connection pooling, this is the number of persistent connections to the Connection Broker.

### Syntax

```
unsigned int getMinConnections() const=0;
```

## getOpenConnections()

Returns the number of open connections in the connection pool. When using database resident connection pooling, this is the number of persistent connections to the Connection Broker.

### Syntax

```
unsigned int getOpenConnections() const=0;
```

## getPoolName()

Returns the name of the connection pool.

### Syntax

```
string getPoolName() const=0;
```

## getStmtCacheSize()

Retrieves the size of the statement cache.



**Syntax**

```
unsigned int getStmtCacheSize() const=0;
```

**getTimeOut()**

Returns the time out period of a connection in the connection pool.

**Syntax**

```
unsigned int getTimeOut() const=0;
```

**setErrorOnBusy()**

Specifies that a `SQLException` is to be generated when all connections in the connection pool are busy and no further connections can be opened.

**Syntax**

```
void setErrorOnBusy()=0;
```

**setPoolSize()**

Sets the minimum, maximum, and incremental number of pooled connections for the connection pool.

**Syntax**

```
void setPoolSize(
    unsigned int minConn = 0,
    unsigned int maxConn = 1,
    unsigned int incrConn = 1)=0;
```

Parameter	Description
<code>minConn</code>	The minimum number of connections for the connection pool.
<code>maxConn</code>	The maximum number of connections for the connection pool.
<code>incrConn</code>	The incremental number of connections for the connection pool.

**setStmtCacheSize()**

Enables or disables statement caching. A nonzero value will enable statement caching, with a cache of specified size. A zero value will disable caching.

**Syntax**

```
void setStmtCacheSize(
    unsigned int cacheSize)=0;
```

Parameter	Description
<code>cacheSize</code>	The size of the statement cache.

## setTimeOut()

Sets the time out period for a connection in the connection pool. OCCI will terminate any connections related to this connection pool that have been idle for longer than the time out period specified.

If this attribute is not set, the least recently used sessions will be timed out when pool space is required. Oracle only checks for timed out sessions when it releases a session back to the pool.

### Syntax

```
void setTimeOut(  
    unsigned int connTimeOut = 0)=0;
```

---

Parameter	Description
connTimeOut	The timeout period in number of seconds.

---

## terminateConnection()

Terminates the pooled connection or proxy connection.

### Syntax

```
void terminateConnection(  
    Connection *connection)=0;
```

---

Parameter	Description
connection	The pooled connection or proxy connection to terminate.

---

## Consumer Class

The `Consumer` class supports dequeuing of `Messages` and controls the dequeuing options.

**Table 13–14 Enumerated Values Used by Consumer Class**

Attribute	Options
DequeueMode	<ul style="list-style-type: none"> <li>▪ <code>DEQ_BROWSE</code> indicates that the message should be read without acquiring a lock; equivalent to a <code>SELECT</code>.</li> <li>▪ <code>DEQ_LOCKED</code> indicates that the message should be read. Get its write lock, which lasts <code>s</code> for the duration of the transaction; equivalent to a <code>SELECT FOR UPDATE</code>.</li> <li>▪ <code>DEQ_REMOVE</code> indicates that the message should be read. Update or delete it; the message can be retained in the queue table based on the retention properties. This is the default setting.</li> <li>▪ <code>DEQ_REMOVE_NODATA</code> indicates that the receipt of the message should be confirmed, but its actual content should not be delivered.</li> </ul>
Navigation	<ul style="list-style-type: none"> <li>▪ <code>DEQ_FIRST_MSG</code> indicates that the first available message on the queue that matches the search criteria must be retrieved. Resets the position to the beginning of the queue.</li> <li>▪ <code>DEQ_NEXT_TRANSACTION</code> indicates that the next available message on the queue that matches the search criteria must be retrieved. If the previous message belongs to a message group, AQ will retrieve the next available message that matches the search criteria and belongs to the message group. This is the default setting.</li> <li>▪ <code>DEQ_NEXT_MSG</code> indicates that the remainder of the current transaction group, if any, should be skipped. The first message of the next transaction group will then be retrieved. This option can only be used if message grouping is enabled for the current queue.</li> </ul>
Visibility	<ul style="list-style-type: none"> <li>▪ <code>DEQ_IMMEDIATE</code> indicates that the dequeued message is not part of the current transaction. It constitutes a transaction on its own.</li> <li>▪ <code>DEQ_ON_COMMIT</code> indicates that the dequeue will be part of the current transaction. This is the default setting.</li> </ul>
DequeueWaitOption	<ul style="list-style-type: none"> <li>▪ <code>DEQ_WAIT_FOREVER</code> indicates that the consumer will wait for the <code>Message</code> indefinitely.</li> <li>▪ <code>DEQ_NO_WAIT</code> indicates that there should be not wait if there are no messages on the queue.</li> </ul>

**Table 13–15 Summary of Consumer Methods**

Method	Description
<a href="#">Consumer()</a> on page 13-68	Consumer class constructor.
<a href="#">getConsumerName()</a> on page 13-69	Retrieves the name of the <code>Consumer</code> .
<a href="#">getCorrelationId()</a> on page 13-69	Retrieves the correlation id of the message that is to be dequeued.
<a href="#">getDequeueMode()</a> on page 13-69	Retrieves the dequeue mode of the <code>Consumer</code> .
<a href="#">getMessageIdToDequeue()</a> on page 13-69	Retrieves the id of the message that will be dequeued.
<a href="#">getQueueName()</a> on page 13-70	Gets the name of the queue used by the consumer.

**Table 13–15 (Cont.) Summary of Consumer Methods**

Method	Description
<a href="#">getPositionOfMessage()</a> on page 13-69	Retrieves the position of the Message that will be dequeued.
<a href="#">getTransformation()</a> on page 13-70	Retrieves the transformation applied before a Message is dequeued.
<a href="#">getVisibility()</a> on page 13-70	Retrieves the transactional behavior of the dequeue operation.
<a href="#">getWaitTime()</a> on page 13-70	Retrieves the specified behavior of the Consumer when waiting for a Message with matching search criteria.
<a href="#">isNull()</a> on page 13-70	Tests whether the Consumer object is NULL.
<a href="#">operator=()</a> on page 13-70	Assignment operator for the Consumer class.
<a href="#">receive()</a> on page 13-71	Receives and dequeues a Message
<a href="#">setAgent()</a> on page 13-71	Sets the Agent's name and address (queue name) on the consumer.
<a href="#">setConsumerName()</a> on page 13-71	Sets the Consumer name.
<a href="#">setCorrelationId()</a> on page 13-72	Specifies the correlation identifier of the message to be dequeued.
<a href="#">setDequeueMode()</a> on page 13-72	Specifies the locking behavior associated with dequeuing.
<a href="#">setMessageIdToDequeue()</a> on page 13-72	Specifies the identifier of the Message to be dequeued.
<a href="#">setNull()</a> on page 13-72	Nullifies the Consumer; frees the memory associated with this object.
<a href="#">setPositionOfMessage()</a> on page 13-73	Specifies position of the Message to be retrieved.
<a href="#">setQueueName()</a> on page 13-73	Specifies the name of a queue prior to dequeuing Messages.
<a href="#">setTransformation()</a> on page 13-73	Specifies transformation applied before dequeuing a Message.
<a href="#">setVisibility()</a> on page 13-73	Specifies if Message should be dequeued as part of the current transaction.
<a href="#">setWaitTime()</a> on page 13-74	Specifies wait conditions if there are no Messages with matching criteria.

## Consumer()

Consumer class constructor.

Syntax	Description
<code>Consumer(     const Connection *conn);</code>	Creates a new Consumer object with the specified Connection handle.
<code>Consumer(     const Connection *conn     const Agent&amp; agent);</code>	Creates a new Consumer object with specified Connection and properties of the specified Agent.
<code>Consumer(     const Connection *conn,     const string&amp; queue);</code>	Creates a new Consumer object with specified Connection and queue.

Syntax	Description
<pre>Consumer(     const Consumer&amp; consumer);</pre>	Copy constructor.

Parameter	Description
conn	The connection in which the Consumer is created.
agent	Agent assigned to the Consumer.
queue	Queue at which the Consumer retrieves messages.
consumer	Original Consumer object.

## getConsumerName()

Retrieves the name of the Consumer.

### Syntax

```
string getConsumerName() const;
```

## getCorrelationId()

Retrieves the correlation id of the message that is to be dequeued.

### Syntax

```
string getCorrelationId() const;
```

## getDequeueMode()

Retrieves the dequeue mode of the Consumer. DequeueMode is defined in [Table 13-14](#) on page 13-67.

### Syntax

```
DequeueMode getDequeueMode() const;
```

## getMessageIdToDequeue()

Retrieves the id of the message that will be dequeued.

### Syntax

```
Bytes getMessageToDequeue() const;
```

## getPositionOfMessage()

Retrieves the position, or navigation, of the message that will be dequeued. Navigation is defined in [Table 13-14](#) on page 13-67.

**Syntax**

```
Navigation getPositionOfMessage() const;
```

**getQueueName()**

Gets the name of the queue used by the consumer.

**Syntax**

```
string getQueueName() const;
```

**getTransformation()**

Retrieves the transformation applied before a `Message` is dequeued.

**Syntax**

```
string getTransformation() const;
```

**getVisibility()**

Retrieves the transactional behavior of the dequeue operation, or visibility. `Visibility` is defined in [Table 13-14](#) on page 13-67.

**Syntax**

```
Visibility getVisibility() const;
```

**getWaitTime()**

Retrieves the specified behavior of the `Consumer` when waiting for a `Message` with matching search criteria. `DequeWaitOption` is defined in [Table 13-14](#) on page 13-67.

**Syntax**

```
DequeWaitOption getWaitTime() const;
```

**isNull()**

Tests whether the `Consumer` object is `NULL`. If the `Consumer` object is `NULL`, `TRUE` is returned; otherwise, `FALSE` is returned.

**Syntax**

```
bool isNull() const;
```

**operator=()**

Assignment operator for `Consumer` class.

**Syntax**

```
void operator=(  
    const Consumer& consumer);
```

Parameter	Description
consumer	The original Consumer.

## receive()

Receives and dequeues a Message.

### Syntax

```
Message receive(
    Message::PayloadType pType,
    const string& type="",
    const string& schema="");
```

Parameter	Description
pType	The type of payload expected. Payload Type is defined in <a href="#">Table 13-14</a> on page 13-67.
type	The type of the payload when type is OBJECT.
schema	The schema in which the type is defined when pType is OBJECT.

## setAgent()

Sets the Agent's name and address (queue name) on the consumer.

### Syntax

```
void setAgent(
    const Agent& agent);
```

Parameter	Description
agent	Name of the Agent.

## setConsumerName()

Sets the Consumer name. Only messages with matching consumer name can be accessed. If a queue is not set up for multiple consumer, this option should be set to NULL.

### Syntax

```
void setConsumerName(
    const string& name);
```

Parameter	Description
name	Name of the Consumer.

## setCorrelationId()

Specifies the correlation identifier of the message to be dequeued. Special pattern matching characters, such as the percent sign (%) and the underscore(\_) can be used. If several messages satisfy the pattern, the order of dequeuing is undetermined.

### Syntax

```
void setCorrelationId(
    const string& id);
```

Parameter	Description
id	The identifier of the Message.

## setDequeueMode()

Specifies the locking behavior associated with dequeuing.

### Syntax

```
void setDequeueMode(
    DequeueMode mode);
```

Parameter	Description
mode	Behavior of enqueueing. DequeueMode is defined in <a href="#">Table 13-14</a> on page 13-67.

## setMessageIdToDequeue()

Specifies the identifier of the Message to be dequeued.

### Syntax

```
void setMessageIdToDequeue(
    const Bytes& msgid);
```

Parameter	Description
msgid	Identifier of the Message to be dequeued.

## setNull()

Nullifies the Consumer; frees the memory associated with this object.

### Syntax

```
void setNull();
```



## setPositionOfMessage()

Specifies position of the Message to be retrieved.

### Syntax

```
void setPositionOfMessage(
    Navigation pos);
```

Parameter	Description
pos	Position of the message, <i>Navigation</i> , is defined in <a href="#">Table 13-14</a> on page 13-67.

## setQueueName()

Specifies the name of a queue prior to dequeuing Messages. Typically used when dequeuing multiple messages from the same queue.

### Syntax

```
void setQueueName(
    const string& queue);
```

Parameter	Description
queue	The name of a valid queue in the database.

## setTransformation()

Specifies transformation applied before dequeuing the Message.

### Syntax

```
void setTransformation(
    string &fName);
```

Parameter	Description
fName	SQL transformation function.

## setVisibility()

Specifies if Message should be dequeued as part of the current transaction. Visibility parameter is ignored when in DEQ\_BROWSE mode.

### Syntax

```
void setVisibility(
    Visibility option);
```

Parameter	Description
option	Visibility option being set, defined in <a href="#">Table 13-14</a> on page 13-67.

## setWaitTime()

Specifies wait conditions if there are no Messages with matching criteria. The `wait` parameter is ignored if messages in the same group are being dequeued.

### Syntax

```
void setWaitTime(  
    DequeWaitOption wait);
```

---

Parameter	Description
wait	Waiting conditions. <code>DequeWaitOption</code> is defined in <a href="#">Table 13-14</a> on page 13-67.

---

## Date Class

The Date class specifies the abstraction for a SQL DATE data item. The Date class also adds formatting and parsing operations to support the OCCI escape syntax for date values.

Since SQL92 DATE is a subset of Oracle Date, this class can be used to support both.

Objects from the Date class can be used as standalone class objects in client side numerical computations and also used to fetch from, and set to, the database.

### **Example 13–5 How to Get a Date from Database and Use it in Standalone Calculations**

This example demonstrates a Date column value being retrieved from the database, a bind using a Date object, and a computation using a standalone Date object.

```

/* Create a connection */
Environment *env = Environment::createEnvironment(Environment::DEFAULT);
Connection *conn = env->createConnection(user, passwd, db);

/* Create a statement and associate a DML statement to it */
string sqlStmt = "SELECT job-id, start_date from JOB_HISTORY
                 where end_date = :x";
Statement *stmt = conn->createStatement(sqlStmt);

/* Create a Date object and bind it to the statement */
Date edate(env, 2000, 9, 3, 23, 30, 30);
stmt->setDate(1, edate);
ResultSet *rset = stmt->executeQuery();

/* Fetch a date from the database */
while(rset->next())
{
    Date sd = rset->getDate(2);
    Date temp = sd;    /*assignment operator */
    /* Methods on Date */
    temp.getDate(year, month, day, hour, minute, second);
    temp.setMonths(2);
    IntervalDS inter = temp.daysBetween(sd);
    .
    .
}

```

**Table 13–16 Summary of Date Methods**

Method	Summary
<a href="#">Date()</a> on page 13-76	Date class constructor.
<a href="#">addDays()</a> on page 13-77	Returns a Date object with <i>n</i> days added.
<a href="#">addMonths()</a> on page 13-77	Returns a Date object with <i>n</i> months added.
<a href="#">daysBetween()</a> on page 13-77	Returns the number of days between the current Date object and the date specified.
<a href="#">fromBytes()</a> on page 13-77	Convert an external Bytes representation of a Date object to a Date object.
<a href="#">fromText()</a> on page 13-78	Convert the date from a given input string with format and NLS parameters specified.

**Table 13–16 (Cont.) Summary of Date Methods**

Method	Summary
<a href="#">getDate()</a> on page 13-78()	Returns the date and time components of the <code>Date</code> object.
<a href="#">getSystemDate()</a> on page 13-79	Returns a <code>Date</code> object containing the system date.
<a href="#">isNull()</a> on page 13-79	Returns <code>TRUE</code> if <code>Date</code> is <code>NULL</code> ; otherwise returns <code>false</code> .
<a href="#">lastDay()</a> on page 13-79	Returns a <code>Date</code> that is the last day of the month.
<a href="#">nextDay()</a> on page 13-79	Returns a <code>Date</code> that is the date of the next day of the week.
<a href="#">operator=()</a> on page 13-80	Assigns the values of a date to another.
<a href="#">operator==(())</a> on page 13-80	Returns <code>TRUE</code> if <code>a</code> and <code>b</code> are the same, <code>false</code> otherwise.
<a href="#">operator!=(())</a> on page 13-80	Returns <code>TRUE</code> if <code>a</code> and <code>b</code> are unequal, <code>false</code> otherwise.
<a href="#">operator&gt;()</a> on page 13-81	Returns <code>TRUE</code> if <code>a</code> is past <code>b</code> , <code>false</code> otherwise.
<a href="#">operator&gt;=()</a> on page 13-81	Returns <code>TRUE</code> if <code>a</code> is past <code>b</code> or equal to <code>b</code> , <code>false</code> otherwise.
<a href="#">operator=()</a> on page 13-80	Returns <code>TRUE</code> if <code>a</code> is before <code>b</code> , <code>false</code> otherwise.
<a href="#">operator&gt;()</a> on page 13-81	Returns <code>TRUE</code> if <code>a</code> is before <code>b</code> , or equal to <code>b</code> , <code>false</code> otherwise.
<a href="#">setDate()</a> on page 13-82	Sets the date from the date components input.
<a href="#">setNull()</a> on page 13-82	Sets the object state to <code>NULL</code> .
<a href="#">toBytes()</a> on page 13-83	Converts the <code>Date</code> object into an external <code>Bytes</code> representation.
<a href="#">toText()</a> on page 13-83	Returns the <code>Date</code> object as a string.
<a href="#">toZone()</a> on page 13-83	Returns a <code>Date</code> object converted from one time zone to another.

## Date()

Date class constructor.

Syntax	Description
<code>Date();</code>	Creates a <code>NULL</code> <code>Date</code> object.
<code>Date(     const Date &amp;srcDate);</code>	Creates a copy of a <code>Date</code> object.
<code>Date(     const Environment *envp,     int year = 1,     unsigned int month = 1,     unsigned int day = 1,     unsigned int hour = 0,     unsigned int minute = 0,     unsigned int seconds = 0);</code>	Creates a <code>Date</code> object using integer parameters.

Parameter	Description
<code>year</code>	-4712 to 9999, except 0

Parameter	Description
month	1 to 12
day	1 to 31
minutes	0 to 59
seconds	0 to 59

## addDays()

Adds a specified number of days to the `Date` object and returns the new date.

### Syntax

```
Date addDays(
    int val) const;
```

Parameter	Description
val	The number of days to be added to the current <code>Date</code> object.

## addMonths()

Adds a specified number of months to the `Date` object and returns the new date.

### Syntax

```
Date addMonths(
    int val) const;
```

Parameter	Description
val	The number of months to be added to the current <code>Date</code> object.

## daysBetween()

Returns the number of days between the current `Date` object and the `date` specified.

### Syntax

```
IntervalDS daysBetween(
    const Date &date) const;
```

Parameter	Description
date	The date to be used to compute the days between.

## fromBytes()

Converts a `Bytes` object to a `Date` object.

**Syntax**

```
void fromBytes(
    const Bytes &byteStream,
    const Environment *envp = NULL);
```

Parameter	Description
byteStream	Date in external format in the form of Bytes.
envp	The OCCI environment.

**fromText()**

Sets Date object to value represented by a string or UString.

The value is interpreted based on the `fmt` and `nlsParam` parameters. In cases where `nlsParam` is not passed, the Globalization Support settings of the `envp` parameter are used.

**See Also:** *Oracle Database SQL Language Reference* for information on `TO_DATE`

Syntax	Description
<pre>void fromText(     const string &amp;datestr,     const string &amp;fmt = "",     const string &amp;nlsParam = "",     const Environment *envp = NULL);</pre>	Sets Date object to value represented by a string.
<pre>void fromText(     const UString &amp;datestr,     const UString &amp;fmt,     const UString &amp;nlsParam,     const Environment *envp = NULL);</pre>	Sets Date object to value represented by a UString; globalization enabled.

Parameter	Description
envp	The OCCI environment.
datestr	The date string to be converted to a Date object.
fmt	The format string; default is DD-MON-YY.
nlsParam	The NLS parameters string. If <code>nlsParam</code> is specified, this determines the NLS parameters to be used for the conversion. If <code>nlsParam</code> is not specified, the NLS parameters are picked up from <code>envp</code> .

**getDate()**

Returns the date in the form of the date components year, month, day, hour, minute, seconds.

**Syntax**

```
void getDate(
```

```

int &year,
unsigned int &month,
unsigned int &day,
unsigned int &hour,
unsigned int &min,
unsigned int &seconds) const;

```

Parameter	Description
year	The year component of the date.
month	The month component of the date.
day	The day component of the date.
hour	The hour component of the date.
min	The minutes component of the date.
seconds	The seconds component of the date.

## getSystemDate()

Returns the system date.

### Syntax

```

static Date getSystemDate(
    const Environment *envp);

```

Parameter	Description
envp	The environment in which the system date is returned.

## isNull()

Tests whether the `Date` is `NULL`. If the `Date` is `NULL`, `TRUE` is returned; otherwise, `FALSE` is returned.

### Syntax

```

bool isNull() const;

```

## lastDay()

Returns a date representing the last day of the current month.

### Syntax

```

Date lastDay() const;

```

## nextDay()

Returns a date representing the day after the day of the week specified.

**See Also:** *Oracle Database SQL Language Reference* for information on `TO_DATE`

## operator=()

---

Syntax	Description
<pre>Date nextDay(     const string &amp;dow) const;</pre>	Returns a date representing the day after the day of the week specified.
<pre>Date nextDay(     const UString &amp;dow) const;</pre>	Returns a date representing the day after the day of the week specified.; globalization enabled. The parameter should be in the character set associated with the environment from which the date was created.

Parameter	Description
dow	A string representing the day of the week.

## operator=()

Assigns the date object on the right side of the equal (=) sign to the date object on the left side of the equal (=) sign.

### Syntax

```
Date& operator=(  
    const Date &d);
```

Parameter	Description
date	The date object that is assigned.

## operator==(())

Compares the dates specified. If the dates are equal, TRUE is returned; otherwise, FALSE is returned.

### Syntax

```
bool operator==(  
    const Date &first,  
    const Date &second);
```

Parameter	Description
first	The first date to be compared.
second	The second date to be compared.

## operator!=(())

Compares the dates specified. If the dates are not equal then TRUE is returned; otherwise, FALSE is returned.

### Syntax

```
bool operator!=(  
    const Date &first,  
    const Date &second);
```



Parameter	Description
first	The first date to be compared.
second	The second date to be compared.

## operator>()

Compares the dates specified. If the first date is in the future relative to the second date then `TRUE` is returned; otherwise, `FALSE` is returned. If either date is `NULL` then `FALSE` is returned. If the dates are not the same type then `FALSE` is returned.

### Syntax

```
bool operator>(
    const Date &first,
    const Date &second);
```

Parameter	Description
first	The first date to be compared.
second	The second date to be compared.

## operator>=()

Compares the dates specified. If the first date is in the future relative to the second date or the dates are equal then `TRUE` is returned; otherwise, `FALSE` is returned. If either date is `NULL` then `FALSE` is returned. If the dates are not the same type then `FALSE` is returned.

### Syntax

```
bool operator>=(
    const Date &first,
    const Date &second);
```

Parameter	Description
first	The first date to be compared.
second	The second date to be compared.

## operator<()

Compares the dates specified. If the first date is in the past relative to the second date then `TRUE` is returned; otherwise, `FALSE` is returned. If either date is `NULL` then `FALSE` is returned. If the dates are not the same type then `FALSE` is returned.

### Syntax

```
bool operator<(
    const Date &first,
    const Date &second);
```

Parameter	Description
first	The first date to be compared.
second	The second date to be compared.

## operator<=()

Compares the dates specified. If the first date is in the past relative to the second date or the dates are equal then `TRUE` is returned; otherwise, `FALSE` is returned. If either date is `NULL` then `FALSE` is returned. If the dates are not the same type then `FALSE` is returned.

### Syntax

```
bool operator<=(
    const Date &first,
    const Date &second);
```

Parameter	Description
first	The first date to be compared.
second	The second date to be compared.

## setDate()

Sets the date to the values specified.

### Syntax

```
void setDate(
    int year = 1,
    unsigned int month = 1,
    unsigned int day = 1,
    unsigned int hour = 0,
    unsigned int minute = 0,
    unsigned int seconds = 0);
```

Parameter	Description
year	The argument specifying the year value. Valid values are -4713 through 9999.
month	The argument specifying the month value. Valid values are 1 through 12.
day	The argument specifying the day value. Valid values are 1 through 31.
hour	The argument specifying the hour value. Valid values are 0 through 23.
min	The argument specifying the minutes value. Valid values are 0 through 59.
seconds	The argument specifying the seconds value. Valid values are 0 through 59.

## setNull()

Sets the `Date` to atomically `NULL`.

**Syntax**

```
void setNull();
```

**toBytes()**

Returns the date in `Bytes` representation.

**Syntax**

```
Bytes toBytes() const;
```

**toText()**

Returns a `string` or `UString` with the value of this date formatted using `fmt` and `nlsParam`.

The value is interpreted based on the `fmt` and `nlsParam` parameters. In cases where `nlsParam` is not passed, the Globalization Support settings of the `envp` parameter are used.

**See Also:** *Oracle Database SQL Language Reference* for information on `TO_DATE`

Syntax	Description
<pre>string toText(     const string &amp;fmt = "",     const string &amp;nlsParam = "") const;</pre>	Returns a <code>string</code> with the value of this date formatted using <code>fmt</code> and <code>nlsParam</code> .
<pre>UString toText(     const UString &amp;fmt,     const UString &amp;nlsParam) const;</pre>	Returns a <code>UString</code> with the value of this date formatted using <code>fmt</code> and <code>nlsParam</code> .

Parameter	Description
<code>fmt</code>	The format string; default is <code>DD-MON-YY</code> .
<code>nlsParam</code>	The NLS parameters string. If <code>nlsParam</code> is specified, this determines the NLS parameters to be used for the conversion. If <code>nlsParam</code> is not specified, the NLS parameters are picked up from <code>envp</code> .

**toZone()**

Returns `Date` value converted from one time zone to another.

**Syntax**

```
Date toZone(
    const string &zone1,
    const string &zone2) const;
```

Parameter	Description
<code>zone1</code>	A string representing the time zone to be converted from.
<code>zone2</code>	A string representing the time zone to be converted to.

Valid time zone codes are:

<b>Zone code</b>	<b>Value</b>
AST, ADT	Atlantic Standard or Daylight Time
BST, BDT	Bering Standard or Daylight Time
CST, CDT	Central Standard or Daylight Time
EST, EDT	Eastern Standard or Daylight Time
GMT	Greenwich Mean Time
HST, HDT	Alaska-Hawaii Standard Time or Daylight Time
MST, MDT	Mountain Standard or Daylight Time
NST	Newfoundland Standard Time
PST, PDT	Pacific Standard or Daylight Time
YST, YDT	Yukon Standard or Daylight Time

## Environment Class

The Environment class provides an OCCI environment to manage memory and other resources for OCCI objects.

The application can have multiple OCCI environments. Each environment would have its own heap and thread-safety mutexes.

**Table 13–17 Enumerated Values Used by Environment Class**

Attribute	Options
Mode	<ul style="list-style-type: none"> <li>▪ <code>DEFAULT</code> is used for creating an Environment object; it has no thread safety or object support.</li> <li>▪ <code>OBJECT</code> is for creating an Environment object; it uses object features.</li> <li>▪ <code>SHARED</code> is for creating an Environment object.</li> <li>▪ <code>NO_USERCALLBACKS</code> is for creating an Environment object; it does not support user callbacks.</li> <li>▪ <code>THREADED_MUTEXED</code> is a thread safe mode for creating an Environment object, mutexed internally by OCCI.</li> <li>▪ <code>THREADED_UNMUTEXED</code> is a thread safe mode for creating an Environment object; the client is responsible for mutexing.</li> <li>▪ <code>EVENTS</code> supports registration for event notification used in Oracle Streams Advanced Queuing.</li> <li>▪ <code>USE_LDAP</code> supports registration with LDAP.</li> </ul>

**Table 13–18 Summary of Environment Methods**

Method	Summary
<a href="#">createConnection()</a> on page 13-86	Establishes a connection to the specified database.
<a href="#">createConnectionPool()</a> on page 13-87	Creates a connection pool.
<a href="#">createEnvironment()</a> on page 13-88	Creates an <code>Environment</code> object.
<a href="#">createStatelessConnectionPool()</a> on page 13-89	Creates a stateless connection pool.
<a href="#">enableSubscription()</a> on page 13-90	Enables subscription notification
<a href="#">disableSubscription()</a> on page 13-90	Disables subscription notification
<a href="#">getCacheMaxSize()</a> on page 13-90	Retrieves the Cache Max heap size.
<a href="#">getCacheOptSize()</a> on page 13-90	Retrieves the cache optimal heap size.
<a href="#">getCacheSortedFlush()</a> on page 13-91	Retrieves the setting of the cache sorting flag.
<a href="#">getClientVersion()</a> on page 13-52	Returns the version of the client library.
<a href="#">getCurrentHeapSize()</a> on page 13-91	Returns the current amount of memory allocated to all objects in the current environment.
<a href="#">getLDAPAdminContext()</a> on page 13-91	Returns the administrative context when using LDAP open notification registration.
<a href="#">getLDAPAuthentication()</a> on page 13-91	Returns the authentication mode when using LDAP open notification registration.
<a href="#">getLDAPHost()</a> on page 13-91	Returns the host on which the LDAP server runs.

**Table 13–18 (Cont.) Summary of Environment Methods**

Method	Summary
<a href="#">getLDAPPort()</a> on page 13-91	Returns the port on which the LDAP server is listening.
<a href="#">getMap()</a> on page 13-91()	Returns the Map for the current environment.
<a href="#">getOCIEnvironment()</a> on page 13-92	Returns the OCI environment associated with the current environment.
<a href="#">getXAConnection()</a> on page 13-92	Creates an XA connection to a database.
<a href="#">getXAEnvironment()</a> on page 13-92	Creates an XA <code>Environment</code> object.
<a href="#">releaseXAConnection()</a> on page 13-92	Releases all resources allocated by a <a href="#">getXAConnection()</a> call.
<a href="#">releaseXAEnvironment()</a> on page 13-93	Releases all resources allocated by a <a href="#">getXAEnvironment()</a> call.
<a href="#">setCacheMaxSize()</a> on page 13-93	Specifies the maximum size for the client-side object cache as a percentage of the optimal size.
<a href="#">setCacheOptSize()</a> on page 13-93	Specifies the optimal size for the client-side object cache in bytes.
<a href="#">setCacheSortedFlush()</a> on page 13-93	Specifies whether to sort cache in table order prior to flushing.
<a href="#">setLDAPAdminContext()</a> on page 13-94	Specifies the administrative context for the LDAP client.
<a href="#">setLDAPAuthentication()</a> on page 13-94	Specifies the LDAP authentication mode.
<a href="#">setLDAPHostAndPort()</a> on page 13-94	Specifies the LDAP server host and port.
<a href="#">setLDAPLoginNameAndPassword()</a> on page 13-95	Specifies the login name and password when connecting to an LDAP server.
<a href="#">terminateConnection()</a> on page 13-95	Closes the connection pool and free all related resources.
<a href="#">terminateConnectionPool()</a> on page 13-95	Closes the connection pool and free all related resources.
<a href="#">terminateEnvironment()</a> on page 13-95	Destroys the environment.
<a href="#">terminateStatelessConnectionPool()</a> on page 13-96	Closes the stateless connection pool and free all related resources.

## createConnection()

This method establishes a connection to the database specified.

Syntax	Description
<pre> Connection * createConnection(     const string &amp;userName,     const string &amp;password,     const string &amp;connectString="")=0; </pre>	Creates a default connection.

Syntax	Description
<pre>Connection * createConnection(     const UString &amp;userName,     const UString &amp;password,     const UString &amp;connectString)=0;</pre>	Creates a connection (Unicode support). The client Environment should be initialized in OCCITUTIF16 mode.
<pre>Connection * createConnection(     const string &amp;userName,     const string &amp;password,     const string &amp;connectString,     const string &amp;connectionClass,     const Connection::Purity &amp;purity)=0;</pre>	Creates a connection for database resident connection pooling.
<pre>Connection * createConnection(     const UString &amp;userName,     const UString &amp;password,     const UString &amp;connectString,     const UString &amp;connectionClass     const Connection::Purity &amp;purity)=0;</pre>	Creates a connection for database resident connection pooling (Unicode support). The client Environment should be initialized in OCCITUTIF16 mode.

Parameter	Description
userName	The name of the user with which to connect.
password	The password of the user.
connectString	The database to which the connection is made.
purity	The purity of the connection used for database resident connection pooling; either SELF or NEW.
connectionClass	The connection class used for database resident connection pooling.

## createConnectionPool()

Creates a connection pool based on the parameters specified.

Syntax	Description
<pre>ConnectionPool* createConnectionPool(     const string &amp;poolUserName,     const string &amp;poolPassword,     const string &amp;connectString = "",     unsigned int minConn = 0,     unsigned int maxConn = 1,     unsigned int incrConn = 1)=0;</pre>	Creates a default connection pool.
<pre>ConnectionPool* createConnectionPool(     const UString &amp;poolUserName,     const UString &amp;poolPassword,     const UString &amp;connectString,     unsigned int minConn = 0,     unsigned int maxConn = 1,     unsigned int incrConn = 1)=0;</pre>	Creates a connection pool (Unicode support). The client Environment should be initialized in OCCITUTIF16 mode.

Parameter	Description
poolUserName	The pool user name.

Parameter	Description
poolPassword	The pool password.
connectString	The connection string for the server
minConn	The minimum number of connections in the pool. The minimum number of connections are opened by this method. Additional connections are opened only when necessary. Generally, minConn should be set to the number of concurrent statements the application is expected to run.
maxConn	The maximum number of connections in the pool. Valid values are 1 and greater.
incrConn	The increment by which to increase the number of connections to be opened if the current number of connections is less than maxConn. Valid values are 1 and greater.

## createEnvironment()

Creates an `Environment` object. It is created with the specified memory management functions specified in the `setMemMgrFunctions()` method. If no memory manager functions are specified, then OCCI uses its own default functions. An `Environment` object must eventually be closed to free all the system resources it has acquired.

If the `Mode` is specified is either `THREADED_MUTEXED` or `THREADED_UNMUTEXED` as defined in [Table 13-17](#) on page 13-85, then all three memory management functions must be thread-safe.

Syntax	Description
<pre>static Environment * createEnvironment(     Mode mode = DEFAULT,     void *ctxp = 0,     void *(*malocfp)(void *ctxp,                     size_t size) = 0,     void *(*ralocfp)(void *ctxp,                     void *memptr,                     size_t newsize) = 0,     void (*mfreefp)(void *ctxp,                    void *memptr) = 0);</pre>	Creates a default environment.
<pre>static Environment * createEnvironment(     const string &amp;charset,     const string &amp;ncharset,     Mode mode = DEFAULT,     void *ctxp = 0,     void *(*malocfp)(void *ctxp,                     size_t size) = 0,     void *(*ralocfp)(void *ctxp,                     void *memptr,                     size_t newsize) = 0,     void (*mfreefp)(void *ctxp,                    void *memptr) = 0);</pre>	Creates an environment with the specified character set and NCHAR character set ids (Unicode support). The client <code>Environment</code> should be initialized in <code>OCCIUTF16</code> mode.

Parameter	Description
mode	Values are defined as part of <code>Mode</code> in <a href="#">Table 13-17</a> on page 13-85: <code>DEFAULT</code> , <code>THREADED_MUTEXED</code> , <code>THREADED_UNMUTEXED</code> , <code>OBJECT</code> .



Parameter	Description
ctxp	Context pointer for user-defined memory management function.
size	The size of the memory allocated by user-defined memory allocation function.
newsize	The new size of the memory to be reallocated.
memptr	the existing memory that needs to be reallocated to new size.
malocfp	User-defined memory allocation function.
ralocfp	User-defined memory reallocation function.
mfreefp	User-defined memory free function.
charset	Character set id that will replace the one specified in NLS_LANG.
ncharset	Character set id that will replace the one specified in NLS_NCHAR.

## createStatelessConnectionPool()

Creates a `StatelessConnectionPool` object with specified pool attributes.

Syntax	Description
<pre>StatelessConnectionPool* createStatelessConnectionPool(     const string &amp;poolUserName,     const string &amp;poolPassword,     const string connectString="",     unsigned int maxConn=1,     unsigned int minConn=0,     unsigned int incrConn=1,     StatelessConnectionPool::PoolType         pType=StatelessConnectionPool::HETEROGENEOUS);</pre>	Support for string.
<pre>StatelessConnectionPool* createStatelessConnectionPool(     const UString &amp;poolUserName,     const UString &amp;poolPassword,     const UString &amp;connectString,     unsigned int maxConn = 1,     unsigned int minConn = 0,     unsigned int incrConn = 1,     StatelessConnectionPool::PoolType         pType=StatelessConnectionPool::HETEROGENEOUS);</pre>	Support for UString.

Parameter	Description
poolUserName	The pool user name.
poolPassword	The pool password.
connectString	The connection string for the server.
maxConn	The maximum number of connections that can be opened the pool; additional sessions cannot be open.
minConn	The number of connections initially created in a pool. This parameter is considered only if the <code>PoolType</code> is set to <code>HOMOGENEOUS</code> , as defined in <a href="#">Table 13-40</a> on page 13-202.

Parameter	Description
incrConn	The number of connections by which to increment the pool if all open connections are busy, up to a maximum open connections specified by maxConn parameter. This parameter is considered only if the PoolType is set to HOMOGENEOUS, as defined in <a href="#">Table 13-40</a> on page 13-202.
pType	The PoolType of the connection pool, defined in <a href="#">Table 13-40</a> on page 13-202.

## enableSubscription()

Enables subscription notification.

### Syntax

```
void enableSubscription(  
    const aq::Subscription &sub);
```

Parameter	Description
sub	The Subscription.

## disableSubscription()

Disables subscription notification.

### Syntax

```
void disableSubscription(  
    Subscription &subscr);
```

Parameter	Description
subscr	The Subscription.

## getCacheMaxSize()

Retrieves the maximum size of the cache.

### Syntax

```
unsigned int getCacheMaxSize() const;
```

## getCacheOptSize()

Retrieves the Cache optimal heap size.

### Syntax

```
unsigned int getCacheOptSize() const;
```

## getCacheSortedFlush()

Retrieves the current setting of the cache sorting flag; TRUE or FALSE.

### Syntax

```
bool getCacheSortedFlush() const;
```

## getCurrentHeapSize()

Returns the amount of memory currently allocated to all objects in this environment.

### Syntax

```
unsigned int getCurrentHeapSize() const;
```

## getLDAPAdminContext()

Returns the administrative context when using LDAP open notification registration.

### Syntax

```
string getLDAPAdminContext() const;
```

## getLDAPAuthentication()

Returns the authentication mode when using LDAP open notification registration.

### Syntax

```
unsigned int getLDAPAuthentication() const;
```

## getLDAPHost()

Returns the host on which the LDAP server runs.

### Syntax

```
string getLDAPHost() const;
```

## getLDAPPort()

Returns the port on which the LDAP server is listening.

### Syntax

```
unsigned int getLDAPPort() const;
```

## getMap()

Returns a pointer to the map for this environment.

**Syntax**

```
Map *getMap() const;
```

**getOCIEnvironment()**

Returns a pointer to the OCI environment associated with this environment.

**Syntax**

```
OCIEnv *getOCIEnvironment() const;
```

**getXAConnection()**

Returns a pointer to an OCCI Connection object that corresponds to the one opened by the XA library.

**Syntax**

```
Connection* getXAConnection(  
    const string &dbname);
```

Parameter	Description
dbname	The database name; same as the optional dbname provided in the Open String (and used in connection to the Resource Manager).

**getXAEnvironment()**

Returns a pointer to an OCCI Environment object that corresponds to the one opened by the XA library.

**Syntax**

```
Environment *getXAEnvironment(  
    const string &dbname);
```

Parameter	Description
dbname	The database name; same as the optional dbname provided in the Open String (and used in connection to the Resource Manager).

**releaseXAConnection()**

Release/deallocate all resources allocated by the [getXAConnection\(\)](#) method.

**Syntax**

```
void releaseXAConnection(  
    Connection* conn);
```

Parameter	Description
conn	The connection returned by the <a href="#">getXAConnection()</a> method.

## releaseXAEnvironment()

Release/deallocate all resources allocated by the [getXAEnvironment\(\)](#) method.

### Syntax

```
void releaseXAEnvironment(
    Environment* env);
```

Parameter	Description
env	The environment returned by the <a href="#">getXAEnvironment()</a> method.

## setCacheMaxSize()

Sets the maximum size for the client-side object cache as a percentage of the optimal size. The default value is 10%.

### Syntax

```
void setCacheMaxSize(
    unsigned int maxSize);
```

Parameter	Description
maxSize	The value of the maximum size, as a percentage.

## setCacheOptSize()

Sets the optimal size for the client-side object cache in bytes. The default value is 8MB.

### Syntax

```
void setCacheOptSize(
    unsigned int optSize);
```

Parameter	Description
optSize	The value of the optimal size, in bytes.

## setCacheSortedFlush()

Sets the cache flushing protocol. By default, objects in cache are flushed in the order they are modified; `flag=FALSE`. To improve server-side performance, set `flag=TRUE`, so that the objects in cache are sorted in table order prior to flushing from client cache.

### Syntax

```
void setCacheSortedFlush(
    bool flag);
```

Parameter	Description
flag	FALSE (default) -- no sorting; TRUE -- sorting in table order

## setLDAPAdminContext()

Sets the administrative context of the client. This is usually the root of the Oracle RDBMS LDAP schema in the LDAP server.

### Syntax

```
void setLDAPAdminContext(
    const string &ctx);
```

Parameter	Description
ctx	The client context

## setLDAPAuthentication()

Specifies the authentication mode. Currently the only supported value is 0x1: Simple authentication; username/password authentication.

### Syntax

```
void setLDAPAuthentication(
    unsigned int mode);
```

Parameter	Description
mode	The authentication mode

## setLDAPHostAndPort()

Specifies the host on which the LDAP server is running, and the port on which it is listening for requests.

### Syntax

```
void setLDAPHostAndPort(
    const string &host,
    unsigned int port);
```

Parameter	Description
host	The host for LDAP
port	The port for LDAP

## setLDAPLoginNameAndPassword()

Specifies the login distinguished name and password used when connecting to an LDAP server.

### Syntax

```
void setLDAPLoginNameAndPassword(
    const string &login,
    const &passwd);
```

Parameter	Description
login	The login name
passwd	The login password

## terminateConnection()

Closes the connection to the environment, and frees all related system resources.

### Syntax

```
void terminateConnection(
    Connection *connection);
```

Parameter	Description
connection	A pointer to the connection instance to be terminated.

## terminateConnectionPool()

Closes the connections in the connection pool, and frees all related system resources.

### Syntax

```
void terminateConnectionPool(
    ConnectionPool *poolPointer);
```

Parameter	Description
poolPointer	A pointer to the connection pool instance to be terminated.

## terminateEnvironment()

Closes the environment, and frees all related system resources.

### Syntax

```
void terminateEnvironment(
    Environment *env);
```

Parameter	Description
env	Environment to be closed.

## terminateStatelessConnectionPool()

Destroys the specified `StatelessConnectionPool`.

### Syntax

```
void terminateStatelessConnectionPool(  
    StatelessConnectionPool* poolPointer,  
    StatelessConnectionPool::DestroyMode mode=StatelessConnectionPool::DEFAULT);
```

Parameter	Description
poolPointer	The <code>StatelessConnectionPool</code> to be destroyed.
mode	DestroyMode as defined <a href="#">Table 13-40</a> on page 13-202: DEFAULT or SPF_FORCE.



## IntervalDS Class

The IntervalDS class encapsulates time interval calculations in terms of days, hours, minutes, seconds, and fractional seconds. Leading field precision will be determined by number of decimal digits in day input. Fraction second precision will be determined by number of fraction digits on input.

**Table 13–19 Fields of IntervalDS Class**

Field	Type	Description
day	int	Day component. Valid values are $-10^9$ through $10^9$ .
hour	int	Hour component. Valid values are $-23$ through $23$ .
minute	int	Minute component. Valid values are $-59$ through $59$ .
second	int	Second component. Valid values are $-59$ through $59$ .
fs	int	Fractional second component. Constructs a NULL IntervalDS object. A NULL intervalDS can be initialized by assignment or calling fromText method. Methods that can be called on NULL intervalDS objects are setName() and isNull().

### Example 13–6 How to Use an Empty IntervalDS Object through Direct Assignment

This example demonstrates how the default constructor creates a NULL value, and how you can assign a non NULL value to a day-second interval and then perform operations on it.

```
Environment *env = Environment::createEnvironment();

// Create a NULL day-second interval
IntervalDS ds;
if(ds.isNull())
    cout << "\n ds is null";

// Assign a non-NULL value to ds
IntervalDS anotherDS(env, "10 20:14:10.2");
ds = anotherDS;

// Now all operations on IntervalDS are valid
int DAY = ds.getDay();
```

### Example 13–7 How to Use an Empty IntervalDS Object Through \*Text() Methods

This example demonstrates how to create a NULL day-second interval, initialize the day-second interval by using the fromText () method, add to the day-second interval by using the += operator, multiply by using the \* operator, compare 2 day-second intervals, and convert a day-second interval to a string by using the toText method:

```
Environment *env = Environment::createEnvironment();

// Create a null day-second interval
IntervalDS ds1

// Initialize a null day-second interval by using the fromText method
ds1.fromText("20 10:20:30.9", "", env);

IntervalDS addWith(env, 2, 1);
```

```

ds1 += addWith;    //call += operator

IntervalDS mulDs1=ds1 * Number(env,10);
                    //call * operator
if(ds1==mulDs1)    //call == operator
    .
    .
string strds=ds1.toText(2,4);
                    //2 is leading field precision
                    //4 is the fractional field precision

```

**Table 13–20 Summary of IntervalDS Methods**

Method	Summary
<a href="#">IntervalDS()</a> on page 13-99	IntervalDS class constructor.
<a href="#">fromText()</a> on page 13-99	Returns an IntervalDS converted from a string.
<a href="#">fromUText()</a> on page 13-100	Returns an IntervalDS converted from a UString.
<a href="#">getDay()</a> on page 13-100	Returns day interval values.
<a href="#">getFracSec()</a> on page 13-100	Returns fractional second interval values.
<a href="#">getFracSec()</a> on page 13-100	Returns hour interval values.
<a href="#">getMinute()</a> on page 13-100	Returns minute interval values.
<a href="#">getSecond()</a> on page 13-101	Returns second interval values.
<a href="#">isNull()</a> on page 13-101	Returns true if IntervalDS is NULL, false otherwise.
<a href="#">operator*()</a> on page 13-101	Returns the product of two IntervalDS values.
<a href="#">operator*=( )</a> on page 13-101	Multiplication assignment.
<a href="#">operator=( )</a> on page 13-101	Simple assignment.
<a href="#">operator==( )</a> on page 13-102	Checks if a and b are equal.
<a href="#">operator!=( )</a> on page 13-102	Checks if a and b are not equal.
<a href="#">operator/( )</a> on page 13-102	Returns an IntervalDS with value ( a / b ).
<a href="#">operator/=( )</a> on page 13-103	Division assignment.
<a href="#">operator&gt;( )</a> on page 13-103	Checks if a is greater than b
<a href="#">operator&gt;=( )</a> on page 13-103	Checks if a is greater than or equal to b.
<a href="#">operator&lt;( )</a> on page 13-103	Checks if a is less than b.
<a href="#">operator&lt;=( )</a> on page 13-104	Checks if a is less than or equal to b.
<a href="#">operator-( )</a> on page 13-104	Returns an IntervalDS with value ( a - b ).
<a href="#">operator-=( )</a> on page 13-104	Subtraction assignment.
<a href="#">operator+( )</a> on page 13-105	Returns the sum of two IntervalDS values.
<a href="#">operator+=( )</a> on page 13-105	Addition assignment.
<a href="#">set()</a> on page 13-105	Sets day-second interval.
<a href="#">setNull()</a> on page 13-106	Sets day-second interval to NULL.
<a href="#">toText()</a> on page 13-106	Converts to a string representation for the interval.
<a href="#">toUText()</a> on page 13-106	Converts to a UString representation for the interval.

## IntervalDS()

IntervalDS class constructor.

Syntax	Description
<code>IntervalDS();</code>	Constructs a NULL IntervalDS object. A NULL IntervalDS can be initialized by assignment or calling <a href="#">fromText()</a> method. Methods that can be called on NULL IntervalDS objects are <a href="#">setName()</a> and <a href="#">isNull()</a> .
<code>IntervalDS(   const Environment *env,   int day = 0,   int hour = 0,   int minute = 0,   int second = 0,   int fs = 0);</code>	Constructs an IntervalDS object within a specified Environment.
<code>IntervalDS(   const IntervalDS &amp;src);</code>	Constructs an IntervalYM object from src.

Parameter	Description
<code>env</code>	The Environment.
<code>day</code>	The day field of IntervalDS.
<code>hour</code>	The hour field of IntervalDS.
<code>minute</code>	The minute field of IntervalDS.
<code>second</code>	The second field of IntervalDS.
<code>fs</code>	The fs field of IntervalDS.
<code>src</code>	The source that the IntervalDS object will be copied from.

## fromText()

Creates the interval from the string specified. The string is converted using the nls parameters associated with the relevant environment. The nls parameters are picked up from env. If env is NULL, the nls parameters are picked up from the environment associated with the instance, if any.

### Syntax

```
void fromText(  
  const string &inpstr,  
  const string &nlsParam = "",  
  const Environment *env = NULL);
```

Parameter	Description
<code>inpstr</code>	Input string representing a day second interval of the form 'days hours:minutes:seconds', for example, '10 20:14:10.2'
<code>nlsParam</code>	The NLS parameter string. If nlsParam is specified, this determines the NLS parameters to be used for the conversion. If nlsParam is not specified, the NLS parameters are picked up from envp.

Parameter	Description
env	Environment whose NLS parameters will be used.

## fromUText()

Creates the interval from the UString specified.

### Syntax

```
void fromUText(  
    const UString &inpstr,  
    const Environment *env=NULL );
```

Parameter	Description
inpstr	Input UString representing a day second interval of the form 'days hours:minutes:seconds', for example, '10 20:14:10.2'
env	The Environment.

## getDay()

Returns the day component of the interval.

### Syntax

```
int getDay() const;
```

## getFracSec()

Returns the fractional second component of the interval.

### Syntax

```
int getFracSec() const;
```

## getHour()

Returns the hour component of the interval.

### Syntax

```
int getHour() const;
```

## getMinute()

Returns the minute component of this interval.

### Syntax

```
int getMinute() const;
```

## getSecond()

Returns the seconds component of this interval.

### Syntax

```
int getSecond() const;
```

## isNull()

Tests whether the interval is NULL. If the interval is NULL then TRUE is returned; otherwise, FALSE is returned.

### Syntax

```
bool isNull() const;
```

## operator\*()

Multiplies an interval by a specified value and returns the result.

### Syntax

```
const IntervalDS operator*(
    const IntervalDS &interval,
    const Number &val);
```

Parameter	Description
interval	Interval to be multiplied.
val	Value by which interval is to be multiplied.

## operator\*=( )

Assigns the product of IntervalDS and a to IntervalDS.

### Syntax

```
IntervalDS& operator*=(
    const IntervalDS &factor);
```

Parameter	Description
factor	A day second interval.

## operator=( )

Assigns the specified value to the interval.

### Syntax

```
IntervalDS& operator=(
    const IntervalDS &src);
```

Parameter	Description
src	Value to be assigned.

## operator==( )

Compares the intervals specified. If the intervals are equal, then `TRUE` is returned; otherwise, `FALSE` is returned. If either interval is `NULL` then `SQLException` is thrown.

### Syntax

```
bool operator==(
    const IntervalDS &first,
    const IntervalDS &second);
```

Parameter	Description
first	The first interval to be compared.
second	The second interval to be compared.

## operator!=( )

Compares the intervals specified. If the intervals are not equal then `TRUE` is returned; otherwise, `FALSE` is returned. If either interval is `NULL` then `SQLException` is thrown.

### Syntax

```
bool operator!=(
    const IntervalDS &first,
    const IntervalDS &second);
```

Parameter	Description
first	The first interval to be compared.
second	The second interval to be compared.

## operator/( )

Returns the result of dividing an interval by a constant value.

### Syntax

```
const IntervalDS operator/(
    const IntervalDS &dividend,
    const Number &factor);
```

Parameter	Description
dividend	The interval to be divided.
factor	Value by which interval is to be divided.

## operator/=()

Assigns the quotient of IntervalDS and val to IntervalDS.

### Syntax

```
IntervalDS& operator/= (
    const IntervalDS &factor);
```

Parameter	Description
factor	A day second interval.

## operator>()

Compares the intervals specified. If the first interval is greater than the second interval then TRUE is returned; otherwise, FALSE is returned. If either interval is NULL then SQLException is thrown.

### Syntax

```
bool operator> (
    const IntervalDS &first,
    const IntervalDS &second);
```

Parameter	Description
first	The first interval to be compared.
second	The second interval to be compared.

## operator>=()

Compares the intervals specified. If the first interval is greater than or equal to the second interval then TRUE is returned; otherwise, FALSE is returned. If either interval is NULL then SQLException is thrown.

### Syntax

```
bool operator>= (
    const IntervalDS &first,
    const IntervalDS &first);
```

Parameter	Description
first	The first interval to be compared.
second	The second interval to be compared.

## operator<()

Compares the intervals specified. If the first interval is less than the second interval then TRUE is returned; otherwise, FALSE is returned. If either interval is NULL then SQLException is thrown.

**Syntax**

```
bool operator<(
    const IntervalDS &first,
    const IntervalDS &second);
```

Parameter	Description
first	The first interval to be compared.
second	The second interval to be compared.

**operator<=()**

Compares the intervals specified. If the first interval is less than or equal to the second interval then TRUE is returned; otherwise, FALSE is returned. If either interval is NULL then SQLException is thrown.

**Syntax**

```
bool operator<=(
    const IntervalDS &first,
    const IntervalDS &second);
```

Parameter	Description
first	The first interval to be compared.
second	The second interval to be compared.

**operator-()**

Returns the difference between the intervals *first* and *second*.

**Syntax**

```
const IntervalDS operator-(
    const IntervalDS &first,
    const IntervalDS &second);
```

Parameter	Description
first	The first interval to be compared.
second	The second interval to be compared.

**operator-=()**

Assigns the difference between IntervalDS and val to IntervalDS.

**Syntax**

```
IntervalDS& operator-=(
    const IntervalDS &val);
```



Parameter	Description
val	A day second interval.

## operator+()

Returns the sum of the intervals specified.

### Syntax

```
const IntervalDS operator+(
    const IntervalDS &first,
    const IntervalDS &second);
```

Parameter	Description
first	The first interval to be compared.
second	The second interval to be compared.

## operator+=()

Assigns the sum of IntervalDS and val to IntervalDS.

### Syntax

```
IntervalDS& operator+=(
    const IntervalDS &val);
```

Parameter	Description
val	A day second interval.

## set()

Sets the interval to the values specified.

### Syntax

```
void set(
    int day,
    int hour,
    int minute,
    int second,
    int fracsec);
```

Parameter	Description
day	Day component.
hour	Hour component.
min	Minute component.
second	Second component.
fracsec	Fractional second component.

## setNull()

Sets the IntervalDS to NULL.

### Syntax

```
void setNull();
```

## toText()

Converts to a string representation for the interval.

### Syntax

```
string toText(
    unsigned int lfprec,
    unsigned int fsprec,
    const string &nlsParam = "") const;
```

Parameter	Description
lfprec	Leading field precision.
fsprec	Fractional second precision.
nlsParam	The NLS parameters string. If nlsParam is specified, this determines the NLS parameters to be used for the conversion. If nlsParam is not specified, the NLS parameters are picked up from envp.

## toUText()

Converts to a UString representation for the interval.

### Syntax

```
UString toUText(
    unsigned int lfprec,
    unsigned int fsprec) const;
```

Parameter	Description
lfprec	Leading field precision.
fsprec	Fractional second precision.

## IntervalYM Class

IntervalYM supports the SQL92 data type Year-Month Interval.

Leading field precision will be determined by number of decimal digits on input.

**Table 13–21 Fields of IntervalYM Class**

Field	Type	Description
year	int	Year component. Valid values are $-10^9$ through $10^9$ .
month	int	Month component. Valid values are $-11$ through $11$ .

### **Example 13–8 How to Use an Empty IntervalYM Object Through Direct Assignment**

This example demonstrates that the default constructor creates a NULL value, and how you can assign a non NULL value to a year-month interval and then perform operations on it:

```
Environment *env = Environment::createEnvironment();

// Create a NULL year-month interval
IntervalYM ym
if(ym.isNull())
    cout << "\n ym is null";

// Assign a non-NULL value to ym
IntervalYM anotherYM(env, "10-30");
ym=anotherYM;

// Now all operations on YM are valid
int yr = ym.getYear();
```

### **Example 13–9 How to Use an IntervalYM Object Through ResultSet and toText() Method**

This example demonstrates how to get the year-month interval column from a result set, add to the year-month interval by using the += operator, multiply by using the \* operator, compare 2 year-month intervals, and convert a year-month interval to a string by using the toText() method.

```
//SELECT WARRANT_PERIOD from PRODUCT_INFORMATION
//obtain result set
resultset->next();

//get interval value from resultset
IntervalYM ym1 = resultset->getIntervalYM(1);

IntervalYM addWith(env, 10, 1);
ym1 += addWith;    //call += operator

IntervalYM mulYm1 = ym1 * Number(env, 10);    //call * operator
if(ym1<mulYm1)    //comparison
    .
    .
string strym = ym1.toText(3);    //3 is the leading field precision
```

**Table 13–22 Summary of IntervalYM Methods**

Method	Summary
<a href="#">IntervalYM()</a> on page 13-108	IntervalYM class constructor.
<a href="#">fromText()</a> on page 13-109	Converts a string into an IntervalYM.
<a href="#">fromUText()</a> on page 13-109	Converts a UString into an IntervalYM.
<a href="#">getMonth()</a> on page 13-110	Returns month interval value.
<a href="#">getYear()</a> on page 13-110	Returns year interval value.
<a href="#">isNull()</a> on page 13-110	Checks if the interval is NULL.
<a href="#">operator*()</a> on page 13-110	Returns the product of two IntervalYM values.
<a href="#">operator*=( )</a> on page 13-110	Multiplication assignment.
<a href="#">operator=( )</a> on page 13-111	Simple assignment.
<a href="#">operator==( )</a> on page 13-111	Checks if a and b are equal.
<a href="#">operator!=( )</a> on page 13-111	Checks if a and b are not equal.
<a href="#">operator/( )</a> on page 13-111	Returns an interval with value (a/b).
<a href="#">operator/=( )</a> on page 13-112	Division assignment.
<a href="#">operator&gt;( )</a> on page 13-112	Checks if a is greater than b.
<a href="#">operator&gt;=( )</a> on page 13-112	Checks if a is greater than or equal to b.
<a href="#">operator&lt;( )</a> on page 13-113	Checks if a is less than b.
<a href="#">operator&lt;=( )</a> on page 13-113	Checks if a is less than or equal to b.
<a href="#">operator-( )</a> on page 13-113	Returns an interval with value (a - b).
<a href="#">operator-=( )</a> on page 13-114	Subtraction assignment.
<a href="#">operator+( )</a> on page 13-114	Returns the sum of two IntervalYM values.
<a href="#">operator+=( )</a> on page 13-114	Addition assignment.
<a href="#">set()</a> on page 13-114	Sets the interval to the values specified.
<a href="#">setNull()</a> on page 13-115	Sets the interval to NULL.
<a href="#">toText()</a> on page 13-115	Converts to a string representation of the interval.
<a href="#">toUText()</a> on page 13-115	Converts to a UString representation of the interval.

## IntervalYM()

IntervalYM class constructor.

Syntax	Description
<code>IntervalYM();</code>	Constructs a NULL IntervalYM object. A NULL IntervalYM can be initialized by assignment or calling <a href="#">operator*()</a> method. Methods that can be called on NULL IntervalYM objects are <a href="#">setName()</a> and <a href="#">isNull()</a> .
<code>IntervalYM(   const Environment *env,   int year = 0,   int month = 0);</code>	Creates an IntervalYM object within the specified Environment.

Syntax	Description
<code>IntervalDS(   const IntervalYM &amp;src);</code>	Copy constructor.

Parameter	Description
<code>env</code>	The Environment.
<code>year</code>	The year field of the IntervalYM object.
<code>month</code>	The month field of the IntervalYM object.
<code>src</code>	The source that the IntervalYM object will be copied from.

## fromText()

This method initializes the interval to the values in `inpStr`. The string is interpreted using the NLS parameters set in the environment.

The NLS parameters are picked up from `env`. If `env` is `NULL`, the NLS parameters are picked up from the environment associated with the instance, if any.

### Syntax

```
void fromText(  
  const string &inpStr,  
  const string &nlsParam = "",  
  const Environment *env = NULL);
```

Parameter	Description
<code>inpStr</code>	Input string representing a year month interval of the form 'year-month'.
<code>nlsParam</code>	The NLS parameters string. If <code>nlsParam</code> is specified, this determines the NLS parameters to be used for the conversion. If <code>nlsParam</code> is not specified, the NLS parameters are picked up from <code>env</code> .
<code>env</code>	Environment whose NLS parameters will be used.

## fromUText()

Creates the interval from the `UString` specified.

### Syntax

```
void fromUText(  
  const UString &inpStr,  
  const Environment *env=NULL );
```

Parameter	Description
<code>inpStr</code>	Input <code>UString</code> representing a year month interval of the form 'year-month'.
<code>env</code>	The Environment.

## getMonth()

This method returns the month component of the interval.

### Syntax

```
int getMonth() const;
```

## getYear()

This method returns the year component of the interval.

### Syntax

```
int getYear() const;
```

## isNull()

This method tests whether the interval is NULL. If the interval is NULL then TRUE is returned; otherwise, FALSE is returned.

### Syntax

```
bool isNull() const;
```

## operator\*()

This method multiplies the interval by a factor and returns the result.

### Syntax

```
const IntervalYM operator*(  
    const IntervalDS &interval  
    const Number &val);
```

Parameter	Description
interval	Interval to be multiplied.
val	Value by which interval is to be multiplied.

## operator\*=( )

This method multiplies the interval by a specified value.

### Syntax

```
IntervalYM& operator*=(  
    const Number &factor);
```

Parameter	Description
factor	Value to be multiplied.

## operator=()

This method assigns the specified value to the interval.

### Syntax

```
IntervalYM& operator=(
    const IntervalYM &src);
```

Parameter	Description
src	Value to be assigned.

## operator==(())

This method compares the intervals specified. If the intervals are equal then `TRUE` is returned; otherwise, `FALSE` is returned. If either interval is `NULL` then `SQLException` is thrown.

### Syntax

```
bool operator==(
    const IntervalYM &first,
    const IntervalYM &second);
```

Parameter	Description
first	The first interval to be compared.
second	The second interval to be compared.

## operator!=(())

This method compares the intervals specified. If the intervals are not equal then `TRUE` is returned; otherwise, `FALSE` is returned. If either interval is `NULL` then `SQLException` is thrown.

### Syntax

```
bool operator!=(
    const IntervalYM &first,
    const IntervalYM &second);
```

Parameter	Description
first	The first interval to be compared.
second	The second interval to be compared.

## operator/()

This method returns the result of dividing the interval by a factor.

**Syntax**

```
const IntervalYM operator/(
    const IntervalYM &dividend,
    const Number &factor);
```

Parameter	Description
dividend	The interval to be divided.
factor	Value by which interval is to be divided.

**operator/=(

---**

This method divides the interval by a factor.

**Syntax**

```
IntervalYM& operator/=(
    const Number &factor);
```

Parameter	Description
factor	A day second interval.

**operator>()

---**

This method compares the intervals specified. If the first interval is greater than the second interval then `TRUE` is returned; otherwise, `FALSE` is returned. If either interval is `NULL` then `SQLException` is thrown.

**Syntax**

```
bool operator>(
    const IntervalYM &first,
    const IntervalYM &second);
```

Parameter	Description
first	The first interval to be compared.
second	The second interval to be compared.

**operator>=()

---**

This method compares the intervals specified. If the first interval is greater than or equal to the second interval then `TRUE` is returned; otherwise, `FALSE` is returned. If either interval is `NULL` then `SQLException` is thrown.

**Syntax**

```
bool operator>=(
    const IntervalYM &first,
    const IntervalYM &second);
```



Parameter	Description
first	The first interval to be compared.
second	The second interval to be compared.

## operator<()

This method compares the intervals specified. If the first interval is less than the second interval then `TRUE` is returned; otherwise, `FALSE` is returned. If either interval is `NULL` then `SQLException` is thrown.

### Syntax

```
bool operator<(
    const IntervalYM &first,
    const IntervalYM &second);
```

Parameter	Description
first	The first interval to be compared.
second	The second interval to be compared.

## operator<=()

This method compares the intervals specified. If the first interval is less than or equal to the second interval then `TRUE` is returned; otherwise, `FALSE` is returned. If either interval is `NULL` then `SQLException` is thrown.

### Syntax

```
bool operator<=(
    const IntervalYM &first,
    const IntervalYM &second);
```

Parameter	Description
first	The first interval to be compared.
second	The second interval to be compared.

## operator-()

This method returns the difference between the intervals specified.

### Syntax

```
const IntervalYM operator-(
    const IntervalYM &first,
    const IntervalYM &second);
```

Parameter	Description
first	The first interval to be compared.

`operator-=( )`

---

Parameter	Description
<code>second</code>	The second interval to be compared.

## `operator-=( )`

This method computes the difference between itself and another interval.

### Syntax

```
IntervalYM& operator-=(  
    const IntervalYM &val);
```

Parameter	Description
<code>val</code>	A day second interval.

## `operator+( )`

This method returns the sum of the intervals specified.

### Syntax

```
const IntervalYM operator+(  
    const IntervalYM &first,  
    const IntervalYM &second);
```

Parameter	Description
<code>first</code>	The first interval to be compared.
<code>second</code>	The second interval to be compared.

## `operator+=( )`

This method assigns the sum of `IntervalYM` and `val` to `IntervalYM`.

### Syntax

```
IntervalYM& operator+=(  
    const IntervalYM &val);
```

Parameter	Description
<code>val</code>	A day second interval.

## `set( )`

This method sets the interval to the values specified.

### Syntax

```
void set(  
    int year,
```

```
int month);
```

Parameter	Description
year	Year component. Valid values are $-10^9$ through $10^9$ .
month	Month component. Valid values are $-11$ through $11$ .

## setNull()

This method sets the interval to NULL.

### Syntax

```
void setNull();
```

## toText()

This method returns the string representation of the interval.

### Syntax

```
string toText(
    unsigned int lfpref,
    const string &nlsParam = "") const;
```

Parameter	Description
lfpref	Leading field precision.
nlsParam	The NLS parameters string. If nlsParam is specified, this determines the NLS parameters to be used for the conversion. If nlsParam is not specified, the NLS parameters are picked up from envp.

## toUText()

Converts to a UString representation for the interval.

### Syntax

```
UString toUText(
    unsigned int lfpref) const;
```

Parameter	Description
lfpref	Leading field precision.

## Listener Class

The `Listener` class encapsulates the ability to listen for `Messages`, on behalf of registered `Agents`, at specified queues.

**Table 13–23 Summary of Listener Methods**

Method	Summary
<code>Listener()</code> on page 13-116	<code>Listener</code> class constructor.
<code>getAgentList()</code> on page 13-116	Retrieves the list of <code>Agents</code> for which the <code>Listener</code> provides its services.
<code>getTimeoutForListen()</code> on page 13-117	Retrieves the time out for a call.
<code>listen()</code> on page 13-117	Listens for <code>Messages</code> and returns the name of the <code>Agent</code> for whom a <code>Message</code> is intended.
<code>setAgentList()</code> on page 13-117	Specifies the list of <code>Agents</code> for which the <code>Listener</code> provides its services.
<code>setTimeoutForListen()</code> on page 13-117	Specifies the time out for a <code>listen()</code> call.

## Listener()

`Listener` class constructor.

Syntax	Description
<code>Listener(const Connection* conn);</code>	Creates a <code>Listener</code> object.
<code>Listener(const Connection* conn, vector&lt;Agent&gt; &amp;aglist, int waitTime=0);</code>	Creates a <code>Listener</code> object and sets the list of <code>Agents</code> on behalf of which it listens on queues. Also sets the waiting time; default: no waiting.

Parameter	Description
<code>conn</code>	The connection of the new <code>Listener</code> object.
<code>aglist</code>	The list of agents on behalf of which the <code>Listener</code> object waits on queues; clients of this <code>Listener</code> .
<code>waitTime</code>	The time to wait on queues for messages of interest for the clients; in seconds.

## getAgentList()

Retrieves the list of `Agents` for which the `Listener` provides its services.

### Syntax

```
vector<Agent> getAgentList() const;
```

## getTimeoutForListen()

Retrieves the time out for a call.

### Syntax

```
int getTimeoutForListen() const;
```

## listen()

Listens for Messages on behalf of specified Agents for the amount of time specified by a previous [setTimeoutForListen\(\)](#) call. Returns the Agent for which there is a Message.

### Syntax

```
Agent listen();
```

---

**Note:** This is a blocking call. Prior to this call, complete the following steps:

- Registers each Agent listener through a [setAgentList\(\)](#) call.
  - Make a blocking call to [setTimeoutForListen\(\)](#) that will return when a Message for one of the Agents on the list arrives. If no Messages arrive before the wait time expires, the call returns an error.
- 

## setAgentList()

Specifies the list of Agents for which the Listener provides its services.

### Syntax

```
void setAgentList(
    vector<Agent>& agList);
```

Parameter	Description
agList	The list of Agents.

## setTimeoutForListen()

Specifies the time out for a [listen\(\)](#) call.

### Syntax

```
void setTimeoutForListen(
    int waitTime);
```

Parameter	Description
waitTime	The time interval, in seconds, during which the Listener is waiting for Messages at specified queues.

## Map Class

The `Map` class is used to store the mapping of the SQL structured type to C++ classes.

For each user defined type, the Object Type Translator (OTT) generates a C++ class declaration and implements the static methods `readSQL()` and `writeSQL()`. The `readSQL()` method is called when the object from the server appears in the application as a C++ class instance. The `writeSQL()` method is called to marshal the object in the application cache to server data when it is being written / flushed to the server. The `readSQL()` and `writeSQL()` methods generated by OTT are based upon the OCCI standard C++ mappings.

If you want to override the standard OTT generated mappings with customized mappings, you must implement a custom C++ class along with the `readSQL()` and `writeSQL()` methods for each SQL structured type you need to customize. In addition, you must add an entry for each such class into the `Map` member of the `Environment`.

### put()

Adds a map entry for the type, `type_name`, that you want to customize; you must implement the `type_name` C++ class.

You must then add this information into a map object, which should be registered with the connection if the user wants the standard mappings to overridden. This registration can be done by calling the this method after the environment is created passing the environment.

Syntax	Description
<pre>void put(     const string &amp;schemaType,     void *(*rSQL)(void *),     void (*wSQL)(void *, void *));</pre>	Registers a type and its corresponding C++ <code>readSQL</code> and <code>writeSQL</code> functions.
<pre>void put(     const string&amp; schName,     const string&amp; typeName,     void *(*rSQL)(void *),     void (*wSQL)(void *, void *));</pre>	Registers a type and its corresponding C++ <code>readSQL</code> and <code>writeSQL</code> functions; multibyte support.
<pre>void put(     const UString&amp; schName,     const UString&amp; typeName,     void *(*rSQL)(void *),     void (*wSQL)(void *, void *));</pre>	Registers a type and its corresponding C++ <code>readSQL</code> and <code>writeSQL</code> functions; unicode support.

Parameter	Description
<code>schemaType</code>	The schema and typename, separated by ".", like <code>HR.TYPE1</code>
<code>schName</code>	Name of the schema
<code>typeName</code>	Name of the type
<code>rSQL</code>	The <code>readSQL</code> function pointer of the C++ class that corresponds to the type
<code>wSQL</code>	The <code>writeSQL</code> function pointer of the C++ class that corresponds to the type

## Message Class

A message is the unit that is enqueued dequeued. A `Message` object holds both its content, or payload, and its properties. This class provides methods to get and set message properties.

**Table 13–24 Enumerated Values Used by Message Class**

Attribute	Options
<code>MessageState</code>	<ul style="list-style-type: none"> <li>■ <code>MSG_WAITING</code> indicates that the message delay time has not been reached</li> <li>■ <code>MSG_READY</code> indicates that the message is ready to be processed</li> <li>■ <code>MSG_PROCESSED</code> indicates that the message has been processed, and is being retained</li> <li>■ <code>MSG_EXPIRED</code> indicates that the message has been moved to the exception queue.</li> </ul>
<code>PayloadType</code>	<ul style="list-style-type: none"> <li>■ <code>RAW</code></li> <li>■ <code>ANYDATA</code></li> <li>■ <code>OBJECT</code></li> </ul>

**Table 13–25 Summary of Message Methods**

Method	Summary
<a href="#">Message()</a> on page 13-120	Message class constructor.
<a href="#">getAnyData()</a> on page 13-120	Retrieves <code>AnyData</code> payload of the message.
<a href="#">getAttemptsToDequeue()</a> on page 13-121	Retrieves the number of attempts made to dequeue the message.
<a href="#">getBytes()</a> on page 13-121	Retrieves <code>Bytes</code> payload of the message.
<a href="#">getCorrelationId()</a> on page 13-121	Retrieves the identification string.
<a href="#">getDelay()</a> on page 13-121	Retrieves delay with which message was enqueued.
<a href="#">getExceptionQueueName()</a> on page 13-121	Retrieves name of queue to which <code>Message</code> is moved when it cannot be processed.
<a href="#">getExpiration()</a> on page 13-121	Retrieves the expiration of the message.
<a href="#">getMessageEnqueuedTime()</a> on page 13-122	Retrieves time at which message was enqueued.
<a href="#">getMessageState()</a> on page 13-122	Retrieves state of the message at time of enqueueing.
<a href="#">getObject()</a> on page 13-122	Retrieves object payload of the message.
<a href="#">getOriginalMessageId()</a> on page 13-122	Retrieves the <code>Id</code> of the message that generated this message on the last queue.
<a href="#">getPayloadType()</a> on page 13-122	Retrieves the type of the payload.
<a href="#">getPriority()</a> on page 13-122	Retrieves the priority of the message.
<a href="#">getSenderId()</a> on page 13-123	Retrieves the agent who send the <code>Message</code> .
<a href="#">isNull()</a> on page 13-123	Tests whether the <code>Message</code> object is <code>NULL</code> .
<a href="#">operator=()</a> on page 13-123	Assignment operator for <code>Message</code> .
<a href="#">setAnyData()</a> on page 13-123	Specifies <code>AnyData</code> payload of the message.

**Table 13–25 (Cont.) Summary of Message Methods**

Method	Summary
<a href="#">getBytes()</a> on page 13-123	Specifies Bytes payload of the message.
<a href="#">setCorrelationId()</a> on page 13-124	Specifies the identification string.
<a href="#">setDelay()</a> on page 13-124	Specifies the number of seconds to delay the enqueued Message.
<a href="#">setExceptionQueueName()</a> on page 13-124	Specifies the name of the queue to which the Message object will be moved if it cannot be precessed.
<a href="#">setExpiration()</a> on page 13-125	Specifies the duration of time that Message can be dequeued before it expires.
<a href="#">setNull()</a> on page 13-125	Sets the Message object to NULL.
<a href="#">setObject()</a> on page 13-125	Specifies object payload of the message.
<a href="#">setOriginalMessageId()</a> on page 13-125	Specifies id of last queue that generated the Message.
<a href="#">setPriority()</a> on page 13-126	Specifies priority of the Message object.
<a href="#">setRecipientList()</a> on page 13-126	Specifies the list of agents for whom the message is intended.
<a href="#">setSenderId()</a> on page 13-126	Specifies the sender of the Message.

## Message()

Message class constructor.

Syntax	Description
<pre>Message(     const Environment *env);</pre>	Creates a Message object within the specified Environment.
<pre>Message(     const Message&amp; mes);</pre>	Copy constructor.

Parameter	Description
env	The environment of the Message.
mes	The original Message.

## getAnyData()

Retrieves the AnyData payload of the Message.

### Syntax

```
AnyData getAnyData() const;
```



## getAttemptsToDequeue()

Retrieves the number of attempts made to dequeue the message. This property cannot be retrieved while enqueueing.

### Syntax

```
int getAttemptsToDequeue() const;
```

## getBytes()

Retrieves Bytes payload of the Message.

### Syntax

```
Bytes getBytes() const;
```

## getCorrelationId()

Retrieves the identification string.

### Syntax

```
string getCorrelationId() const;
```

## getDelay()

Retrieves the delay (in seconds) with which the Message was enqueued.

### Syntax

```
int getDelay() const;
```

## getExceptionQueueName()

Retrieves the name of the queue to which the Message is moved, in cases when the Message cannot be processed successfully.

### Syntax

```
string getExceptionQueueName() const;
```

## getExpiration()

Retrieves the expiration time of the Message (in seconds). This is the duration for which the message is available for dequeuing.

### Syntax

```
int getExpiration() const;
```

## getMessageEnqueuedTime()

Retrieves the time at which the message was enqueued, in `Date` format. This value is determined by the system, and cannot be set by the user.

### Syntax

```
Date getMessageEnqueuedTime() const;
```

## getMessageState()

Retrieves the state of the message at the time of enqueueing. This parameter cannot be set an enqueueing time. `MessageState` is defined in [Table 13-24](#) on page 13-119.

### Syntax

```
MessageState getMessageState() const;
```

## getObject()

Retrieves object payload of the `Message`.

### Syntax

```
PObject* getObject();
```

## getOriginalMessageId()

Retrieves the original message Id. When a message is propagated from one queue to another, gets the ID to the last queue that generated this message.

### Syntax

```
Bytes getOriginalMessageId() const;
```

## getPayloadType()

Retrieves the type of the payload, as defined for `PayloadType` in [Table 13-24](#) on page 13-119.

### Syntax

```
PayloadType getPayloadType( ) const;
```

## getPriority()

Retrieves the priority of the `Message`.

### Syntax

```
int getPriority() const;
```

## getSenderId()

Retrieves the agent who send the Message.

### Syntax

```
Agent getSenderId() const;
```

## isNull()

Tests whether the Message object is NULL. If the Message object is NULL, then TRUE is returned; otherwise, FALSE is returned.

### Syntax

```
bool isNull() const;
```

## operator=()

Assignment operator for Message.

```
void operator=(  
    const Message& mes);
```

Parameter	Description
mes	Original message.

## setAnyData()

Specifies AnyData payload of the Message.

### Syntax

```
void setAnyData(  
    const AnyData& anydata);
```

Parameter	Description
anydata	Data content of the Message.

## setBytes()

Specifies Bytes payload of the Message.

### Syntax

```
void setBytes(  
    const Bytes& bytes);
```

Parameter	Description
bytes	Data content of the Message.

## setCorrelationId()

Specifies the identification string. This parameter is set at enqueueing time by the Producer. Messages can be dequeued with this id. The id can contain wildcard characters.

### Syntax

```
void setCorrelationId(
    const string& id);
```

Parameter	Description
id	The id; upper limit of 128 bytes.

## setDelay()

Specifies the time (in seconds) to delay the enqueued Message. After the delay ends, the Message is available for dequeuing.

---

**Note:** Dequeuing by `msgid` overrides the delay specification. A Message enqueued with delay will be in the `WAITING` state. Delay is set by the producer of the Message.

---

### Syntax

```
void setDelay(
    int delay);
```

Parameter	Description
delay	The delay.

## setExceptionQueueName()

Specifies the name of the queue to which the Message object will be moved if it cannot be processed successfully. The queue name must be valid.

---

### Note:

- If the exception queue does not exist at the time of the move, the Message will be moved to the default exception queue associated with the queue table; a warning will be logged in the alert file.
  - If the default exception queue is used, the parameter will return a NULL value at enqueueing time; the attribute must refer to a valid queue name.
-

**Syntax**

```
void setExceptionQueueName(
    const string& queue);
```

Parameter	Description
queue	The name of the exception queue.

**setExpiration()**

Specifies the duration time (in seconds) that the `Message` object is available for dequeuing. A `Message` expires after this time.

**Syntax**

```
void setExpiration(
    int exp);
```

Parameter	Description
exp	The duration of expiration.

**setNull()**

Sets the `Message` object to `NULL`. Before the `Connection` is destroyed by the [terminateConnection\(\)](#) call of the [Environment Class](#), all `Message` objects need to be set to `NULL`.

**Syntax**

```
void setNull();
```

**setObject()**

Specifies object payload of the `Message`.

**Syntax**

```
void setObject(
    PObject& pobj);
```

Parameter	Description
pobj	Content of the data

**setOriginalMessageId()**

Sets the Id of the last queue that generated the message, when a message is propagated from one queue to another.

**Syntax**

```
void setOriginalMessageId(
    const Bytes& queue);
```

Parameter	Description
queue	The last queue.

## setPriority()

Specifies the priority of the `Message` object. This property is set during enqueueing time, and can be negative. Default is 0.

### Syntax

```
void setPriority(  
    int priority);
```

Parameter	Description
priority	The priority of the <code>Message</code> .

## setRecipientList()

Specifies the list of `Agents` for whom the `Message` is intended. These recipients are not identical to subscribers of the queue. The property is set during enqueueing. All `Agents` in the list must be valid. The recipient list will override the default subscriber list.

### Syntax

```
void setRecipientList(  
    vector<Agent>& agentList);
```

Parameter	Description
agentList	The list of <code>Agents</code> .

## setSenderId()

Specifies the sender of the `Message`.

### Syntax

```
void setSenderId(  
    const Agent& sender);
```

Parameter	Description
sender	Sender id.

## MetaData Class

A `MetaData` object can be used to describe the types and properties of the columns in a `ResultSet` or the existing schema objects in the database. It also provides information about the database as a whole. The enumerated values of `MetaData` are in [Table 13–26](#), and the summary of its methods is in [Table 13–27](#) on page 13-135.

**Table 13–26 Enumerated Values Used by MetaData Class**

Attribute	Options
<code>ParamType</code>	<p>The parameter types for objects are:</p> <ul style="list-style-type: none"> <li>■ <code>PType_ARG</code> is the argument of a function or procedure.</li> <li>■ <code>PType_COL</code> is the column of a table or view.</li> <li>■ <code>PType_DATABASE</code> is the database.</li> <li>■ <code>PType_FUNC</code> is the function.</li> <li>■ <code>PType_PKG</code> is the package.</li> <li>■ <code>PType_PROC</code> is the procedure.</li> <li>■ <code>PType_SCHEMA</code> is the schema.</li> <li>■ <code>PType_SEQ</code> is the sequence.</li> <li>■ <code>PType_SYN</code> is the synonym.</li> <li>■ <code>PType_TABLE</code> is the table.</li> <li>■ <code>PType_TYPE</code> is the type.</li> <li>■ <code>PType_TYPE_ARG</code> is the argument of a type method.</li> <li>■ <code>PType_TYPE_ATTR</code> is the attribute of a type.</li> <li>■ <code>PType_TYPE_COLL</code> is the collection type information.</li> <li>■ <code>PType_TYPE_METHOD</code> is the method of a type.</li> <li>■ <code>PType_TYPE_RESULT</code> is the results of a method.</li> <li>■ <code>PType_UNK</code> is the object of an unknown type.</li> <li>■ <code>PType_VIEW</code> is the view.</li> </ul>
<code>AttrId</code> common to all parameters	<p>Attributes of all parameters:</p> <ul style="list-style-type: none"> <li>■ <code>Attr_OBJ_ID</code> is the object or schema id.</li> <li>■ <code>Attr_OBJ_NAME</code> is either the database name, or the object name in a schema.</li> <li>■ <code>Attr_OBJ_SCHEMA</code> is the name of the schema describing the object.</li> <li>■ <code>Attr_PType</code> is the type of information described by a parameter, <a href="#">ParamType</a></li> <li>■ <code>Attr_TIMESTAMP</code> is the timestamp of an object.</li> </ul>

**Table 13–26 (Cont.) Enumerated Values Used by MetaData Class**

Attribute	Options
AttrId for Tables and Views	<p>Parameters for a table or view (<a href="#">ParamType</a> of <a href="#">PTYPE_TABLE</a> and <a href="#">PTYPE_VIEW</a>) have the following type-specific attributes:</p> <ul style="list-style-type: none"> <li>■ ATTR_OBJID is the object id</li> <li>■ ATTR_NUM_COLS is the number of columns</li> <li>■ ATTR_LIST_COLUMNS is the column list</li> <li>■ ATTR_REF_TDO is the REF to the TDO of the base type in case of extent tables</li> <li>■ ATTR_IS_TEMPORARY indicates the table is temporary</li> <li>■ ATTR_IS_TYPED indicates the table is typed</li> <li>■ ATTR_DURATION is the duration of a temporary table. Values can be <a href="#">DURATION_SESSION</a>, <a href="#">DURATION_TRANS</a>, and <a href="#">DURATION_NULL</a>, as defined for attribute <a href="#">AttrValues</a></li> </ul>
AttrId for Tables only	<p>Parameters for a tables only (<a href="#">ParamType</a> of <a href="#">PTYPE_TABLE</a>):</p> <ul style="list-style-type: none"> <li>■ ATTR_RDBA indicates the data block address of the segment header</li> <li>■ ATTR_TABLESPACE indicates the tablespace the table resides in</li> <li>■ ATTR_CLUSTERED indicates the table is clustered</li> <li>■ ATTR_PARTITIONED indicates the table is partitioned</li> <li>■ ATTR_INDEX_ONLY indicates the table is index-only</li> </ul>
AttrId for Functions and Procedures	<p>Parameters for functions and procedures (<a href="#">ParamType</a> of <a href="#">PTYPE_FUNC</a> and <a href="#">PTYPE_PROC</a>, respectively):</p> <ul style="list-style-type: none"> <li>■ ATTR_LIST_ARGUMENTS indicates the argument list</li> <li>■ ATTR_IS_INVOKER_RIGHTS indicates the procedure or function has invoker's rights</li> <li>■ ATTR_NAME indicates the name of the procedure or function</li> <li>■ ATTR_OVERLOAD_ID indicates the overloading ID number, relevant when the procedure or function is part of a class and it is overloaded; values returned may be different from direct query of a PL/SQL function or procedure</li> </ul>
AttrId for Packages	<p>Parameters for packages (<a href="#">ParamType</a> of <a href="#">PTYPE_PKG</a>):</p> <ul style="list-style-type: none"> <li>■ ATTR_LIST_SUBPROGRAMS indicates the subprogram list</li> <li>■ ATTR_IS_INVOKER_RIGHTS indicates the procedure or function has invoker's rights</li> </ul>



**Table 13–26 (Cont.) Enumerated Values Used by MetaData Class**

Attribute	Options
AttrId for Types	<p data-bbox="680 260 1235 285">Parameter is for types (<a href="#">ParamType</a> of <a href="#">PTYPE_TYPE</a>):</p> <ul style="list-style-type: none"> <li data-bbox="680 302 1451 407">■ ATTR_REF_TDO indicates the in-memory REF of the type descriptor for the type, if the column type is an object type. If space has not been reserved, then it is allocated implicitly in the cache. The caller can then pin the object.</li> <li data-bbox="680 422 1214 447">■ ATTR_TYPECODE indicates the data type code</li> <li data-bbox="680 462 1344 512">■ ATTR_COLLECTION_TYPECODE indicates the typecode of collection, if type is collection</li> <li data-bbox="680 527 1430 577">■ ATTR_IS_INCOMPLETE_TYPE indicates that this is an incomplete type</li> <li data-bbox="680 592 1425 642">■ ATTR_IS_SYSTEM_TYPE indicates that this is a system generated type</li> <li data-bbox="680 657 1414 707">■ ATTR_IS_PREDEFINED_TYPE indicates that this is a predefined type</li> <li data-bbox="680 722 1430 747">■ ATTR_IS_TRANSIENT_TYPE indicates that this is a transient type</li> <li data-bbox="680 762 1377 812">■ ATTR_IS_SYSTEM_GENERATED_TYPE indicates that this is a system generated type</li> <li data-bbox="680 827 1398 877">■ ATTR_HAS_NESTED_TABLE indicates that this type contains a nested table attribute</li> <li data-bbox="680 892 1406 917">■ ATTR_HAS_LOB indicates that this type contains a LOB attribute</li> <li data-bbox="680 932 1352 982">■ ATTR_HAS_FILE indicates that this type contains a BFILE attribute</li> <li data-bbox="680 997 1430 1047">■ ATTR_COLLECTION_ELEMENT indicates a reference to a collection element</li> <li data-bbox="680 1062 1419 1087">■ ATTR_NUM_TYPE_ATTRS indicates the number of type attributes</li> <li data-bbox="680 1102 1382 1127">■ ATTR_LIST_TYPE_ATTRS indicates the list of type attributes</li> <li data-bbox="680 1142 1438 1167">■ ATTR_NUM_TYPE_METHODS indicates the number of type methods</li> <li data-bbox="680 1182 1398 1207">■ ATTR_LIST_TYPE_METHODS indicates the list of type methods</li> <li data-bbox="680 1222 1352 1247">■ ATTR_MAP_METHOD indicates the map method of the type</li> <li data-bbox="680 1262 1382 1287">■ ATTR_ORDER_METHOD indicates the order method of the type</li> <li data-bbox="680 1302 1451 1327">■ ATTR_IS_INVOKER_RIGHTS indicates the type has invoker's rights</li> <li data-bbox="680 1341 1211 1367">■ ATTR_NAME indicates the type attribute name</li> <li data-bbox="680 1381 1369 1432">■ ATTR_SCHEMA_NAME indicates the schema where the type is created</li> <li data-bbox="680 1446 1279 1472">■ ATTR_IS_FINAL_TYPE indicates this is a final type</li> <li data-bbox="680 1486 1419 1537">■ ATTR_IS_INSTANTIABLE_TYPE indicates this is an instantiable type</li> <li data-bbox="680 1551 1219 1577">■ ATTR_IS_SUBTYPE indicates this is a subtype</li> <li data-bbox="680 1591 1373 1642">■ ATTR_SUPERTYPE_SCHEMA_NAME indicates the name of the schema that contains the supertype</li> <li data-bbox="680 1656 1382 1682">■ ATTR_SUPERTYPE_NAME indicates the name of the supertype</li> </ul>

**Table 13–26 (Cont.) Enumerated Values Used by MetaData Class**

Attribute	Options
AttrId for Type Attributes	<p data-bbox="602 260 1365 285">Parameter is for attributes of types (<a href="#">ParamType</a> of <a href="#">PTYPE_TYPE_ATTR</a>):</p> <ul style="list-style-type: none"> <li data-bbox="602 302 1365 327">■ <code>ATTR_DATA_SIZE</code> indicates the maximum size of the type attribute</li> <li data-bbox="602 344 1365 369">■ <code>ATTR_TYPECODE</code> indicates the data type code</li> <li data-bbox="602 386 1365 411">■ <code>ATTR_DATA_TYPE</code> indicates the data type of the type attribute</li> <li data-bbox="602 428 1365 453">■ <code>ATTR_NAME</code> indicates the name of the procedure or function</li> <li data-bbox="602 470 1365 520">■ <code>ATTR_PRECISION</code> indicates the precision of numeric type attributes.</li> <li data-bbox="602 537 1365 562">■ <code>ATTR_SCALE</code> indicates the scale of the numeric type attributes</li> <li data-bbox="602 579 1365 604">■ <code>ATTR_TYPE_NAME</code> indicates a type name</li> <li data-bbox="602 621 1365 672">■ <code>ATTR_SCHEMA_NAME</code> indicates the name of the schema where the type has been created</li> <li data-bbox="602 688 1365 756">■ <code>ATTR_REF_TDO</code> indicates the in-memory REF of the type, if the column type is an object type. If the space has not been reserved, it is allocated implicitly in the cache. The caller can then pin the object.</li> <li data-bbox="602 772 1365 798">■ <code>ATTR_CHARSET_ID</code> indicates the charset ID</li> <li data-bbox="602 814 1365 840">■ <code>ATTR_CHARSET_FORM</code> indicates the charset form</li> <li data-bbox="602 856 1365 907">■ <code>ATTR_FSPRECISION</code> indicates the fractional seconds precision of a <code>Timestamp</code>, <code>IntervalDS</code> or <code>IntervalYM</code></li> <li data-bbox="602 924 1365 974">■ <code>ATTR_LFPRECISION</code> indicates the leading field precision of an <code>IntervalDS</code> or <code>IntervalYM</code></li> </ul>
AttrId for Type Methods	<p data-bbox="602 991 1365 1041">Parameter is for methods of types (<a href="#">ParamType</a> of <a href="#">PTYPE_TYPE_METHOD</a>):</p> <ul style="list-style-type: none"> <li data-bbox="602 1058 1365 1083">■ <code>ATTR_NAME</code> indicates the name of the procedure or function</li> <li data-bbox="602 1100 1365 1150">■ <code>ATTR_ENCAPSULATION</code> indicates the method's level of encapsulation</li> <li data-bbox="602 1167 1365 1192">■ <code>ATTR_LIST_ARGUMENTS</code> indicates the argument list</li> <li data-bbox="602 1209 1365 1234">■ <code>ATTR_IS_CONSTRUCTOR</code> indicates the method is a constructor</li> <li data-bbox="602 1251 1365 1276">■ <code>ATTR_IS_DESTRUCTOR</code> indicates the method is a destructor</li> <li data-bbox="602 1293 1365 1318">■ <code>ATTR_IS_OPERATOR</code> indicates the method is an operator</li> <li data-bbox="602 1335 1365 1360">■ <code>ATTR_IS_SELFISH</code> indicates the method is selfish</li> <li data-bbox="602 1377 1365 1402">■ <code>ATTR_IS_MAP</code> indicates the method is a map method</li> <li data-bbox="602 1419 1365 1444">■ <code>ATTR_IS_ORDER</code> indicates the method is an order method</li> <li data-bbox="602 1461 1365 1486">■ <code>ATTR_IS_RNDS</code> indicates that the method is in "read no data" state</li> <li data-bbox="602 1503 1365 1554">■ <code>ATTR_IS_RNPS</code> indicates that the method is in a "read no process" state</li> <li data-bbox="602 1570 1365 1621">■ <code>ATTR_IS_WNDS</code> indicates that the method is in "write no data" state</li> <li data-bbox="602 1638 1365 1688">■ <code>ATTR_IS_WNPS</code> indicates that the method is in "write no process" state</li> <li data-bbox="602 1705 1365 1730">■ <code>ATTR_IS_FINAL_METHOD</code> indicates that this is a final method</li> <li data-bbox="602 1747 1365 1797">■ <code>ATTR_IS_INSTANTIABLE_METHOD</code> indicates that this is an instantiable method</li> <li data-bbox="602 1814 1365 1839">■ <code>ATTR_IS_OVERRIDING_METHOD</code> indicates that this is an overriding method</li> </ul>

**Table 13–26 (Cont.) Enumerated Values Used by MetaData Class**

Attribute	Options
AttrId for Collections	<p>Parameter is for collections (ParamType of <a href="#">PTYPE_TYPE_COLL</a>):</p> <ul style="list-style-type: none"> <li>■ ATTR_DATA_SIZE indicates</li> <li>■ ATTR_TYPECODE indicates</li> <li>■ ATTR_DATA_TYPE indicates the data type of the type attribute</li> <li>■ ATTR_NUM_ELEMS indicates the number of elements in a collection</li> <li>■ ATTR_NAME indicates the name of the type attribute</li> <li>■ ATTR_PRECISION indicates the precision of a numeric attribute</li> <li>■ ATTR_SCALE indicates the scale of a numeric attribute</li> <li>■ ATTR_TYPE_NAME indicates the type name</li> <li>■ ATTR_SCHEMA_NAME indicates the schema where the type has been created</li> <li>■ ATTR_REF_TDO indicates the in-memory REF of the type, if the column type is an object type. If the space has not been reserved, it is allocated implicitly in the cache. The caller can then pin the object.</li> <li>■ ATTR_CHARSET_ID indicates the charset id</li> <li>■ ATTR_CHARSET_FORM indicates the charset form</li> </ul>
AttrId for Synonyms	<p>Parameter is for synonyms (ParamType of <a href="#">PTYPE_SYN</a>):</p> <ul style="list-style-type: none"> <li>■ ATTR_OBJID indicates the object id</li> <li>■ ATTR_SCHEMA_NAME indicates the schema name of the synonym translation</li> <li>■ ATTR_NAME indicates a NULL-terminated object name of the synonym translation</li> <li>■ ATTR_LINK indicates a NULL-terminated database link name of the synonym installation</li> </ul>
AttrId for Sequences	<p>Parameter is for sequences (ParamType of <a href="#">PTYPE_SEQ</a>):</p> <ul style="list-style-type: none"> <li>■ ATTR_OBJID indicates the object id</li> <li>■ ATTR_MIN indicates the minimum value</li> <li>■ ATTR_MAX indicates the maximum value</li> <li>■ ATTR_INCR indicates the increment</li> <li>■ ATTR_CACHE indicates the number of sequence numbers cached; 0 if the sequence is not cached</li> <li>■ ATTR_ORDER indicates whether the sequence is ordered</li> <li>■ ATTR_HW_MARK indicates the "high-water mark"</li> </ul>

**Table 13–26 (Cont.) Enumerated Values Used by MetaData Class**

Attribute	Options
AttrId for Columns	<p data-bbox="602 260 1365 285">Parameter is for columns of tables or views (<i>ParamType</i> of <i>PTYPE_COL</i>):</p> <ul style="list-style-type: none"> <li data-bbox="602 302 1317 380">■ <i>ATTR_CHAR_USED</i> indicates the type of length semantics of the column. 0 means byte-length semantics and 1 means character-length semantics.</li> <li data-bbox="602 396 1284 447">■ <i>ATTR_CHAR_SIZE</i> indicates the column character length, or number of characters allowed in a column</li> <li data-bbox="602 464 1325 514">■ <i>ATTR_DATA_SIZE</i> indicates the maximum size of a column, or number of bytes allowed in a column</li> <li data-bbox="602 531 1243 556">■ <i>ATTR_DATA_TYPE</i> indicates the data type of the column</li> <li data-bbox="602 573 1065 598">■ <i>ATTR_NAME</i> indicates the column name</li> <li data-bbox="602 615 1308 640">■ <i>ATTR_PRECISION</i> indicates the precision of numeric columns</li> <li data-bbox="602 657 1203 682">■ <i>ATTR_SCALE</i> indicates the scale of numeric columns</li> <li data-bbox="602 699 1365 749">■ <i>ATTR_IS_NULL</i> indicates 0 if NULL values are not permitted for the column</li> <li data-bbox="602 766 1081 791">■ <i>ATTR_TYPE_NAME</i> indicates a type name</li> <li data-bbox="602 808 1317 858">■ <i>ATTR_SCHEMA_NAME</i> indicates the schema where the type was created</li> <li data-bbox="602 875 1341 926">■ <i>ATTR_REF_TDO</i> indicates the REF for the type, if the column is of object type</li> <li data-bbox="602 942 1162 968">■ <i>ATTR_CHARSET_ID</i> indicates the charset ID</li> <li data-bbox="602 984 1219 1010">■ <i>ATTR_CHARSET_FORM</i> indicates the charset form</li> </ul>

**Table 13–26 (Cont.) Enumerated Values Used by MetaData Class**

Attribute	Options
AttrId for Arguments and Results	<p data-bbox="680 260 1403 312">Parameter for arguments of a procedure or function (<a href="#">PTYPE_ARG</a>), a method (<a href="#">PTYPE_TYPE_ARG</a>), or a result (<a href="#">PTYPE_TYPE_RESULT</a>)</p> <ul style="list-style-type: none"> <li data-bbox="680 327 1170 352">■ ATTR_NAME indicates the argument name</li> <li data-bbox="680 367 1425 392">■ ATTR_POSITION indicates the position of the argument in the list</li> <li data-bbox="680 407 1157 432">■ ATTR_TYPECODE indicates the typecode</li> <li data-bbox="680 447 1174 472">■ ATTR_DATA_TYPE indicates the data type</li> <li data-bbox="680 487 1284 512">■ ATTR_DATA_SIZE indicates the size of the data type</li> <li data-bbox="680 527 1419 552">■ ATTR_PRECISION indicates the precision of a numeric argument</li> <li data-bbox="680 567 1317 592">■ ATTR_SCALE indicates the scale of a numeric argument</li> <li data-bbox="680 606 1174 632">■ ATTR_LEVEL indicates the data type level</li> <li data-bbox="680 646 1435 672">■ ATTR_HAS_DEFAULT indicates whether an argument has a default</li> <li data-bbox="680 686 1442 739">■ ATTR_LIST_ARGUMENTS indicates the list of arguments at the next level, for records or table types</li> <li data-bbox="680 753 1435 806">■ ATTR_IOMODE indicates the argument mode: 0 for IN, 1 for OUT, 2 for IN/OUT</li> <li data-bbox="680 821 1260 846">■ ATTR_RADIX indicates the radix of a number type</li> <li data-bbox="680 861 1369 886">■ ATTR_IS_NULL indicates 0 if NULL values are not permitted</li> <li data-bbox="680 900 1195 926">■ ATTR_TYPE_NAME indicates the type name</li> <li data-bbox="680 940 1409 993">■ ATTR_SCHEMA_NAME indicates the schema name where the type was created</li> <li data-bbox="680 1008 1419 1033">■ ATTR_SUB_NAME indicates the type name for package local types</li> <li data-bbox="680 1047 1448 1121">■ ATTR_LINK indicates a NULL-terminated database link name where the type is defined, for package local types when the package is remote</li> <li data-bbox="680 1136 1435 1188">■ ATTR_REF_TDO is the REF to the TDO of the type if the argument is an object</li> <li data-bbox="680 1203 1247 1228">■ ATTR_CHARSET_ID indicates the charset ID</li> <li data-bbox="680 1243 1300 1268">■ ATTR_CHARSET_FORM indicates the charset form</li> </ul>
AttrId for Schemas	<p data-bbox="680 1289 1297 1314">Parameter is for schemas (<a href="#">ParamType</a> of <a href="#">PTYPE_SCHEMA</a>):</p> <ul style="list-style-type: none"> <li data-bbox="680 1329 1403 1354">■ ATTR_LIST_OBJECTS indicates the list of objects in the schema</li> </ul>
AttrId for Lists	<p data-bbox="680 1377 1317 1402">Parameter is for list of columns, arguments or subprograms:</p> <ul style="list-style-type: none"> <li data-bbox="680 1417 1214 1442">■ ATTR_LIST_COLUMNS indicates a column list</li> <li data-bbox="680 1457 1365 1509">■ ATTR_LIST_ARGUMENTS indicates a procedure or function argument list</li> <li data-bbox="680 1524 1321 1549">■ ATTR_LIST_SUBPROGRAMS indicates a subprogram list</li> <li data-bbox="680 1564 1349 1589">■ ATTR_LIST_TYPE_ATTRIBS indicates a type attribute list</li> <li data-bbox="680 1604 1268 1629">■ ATTR_TYPE_METHODS indicates a type method list</li> <li data-bbox="680 1644 1360 1669">■ ATTR_TYPE_OBJECTS indicates a list of objects in a schema</li> <li data-bbox="680 1684 1395 1709">■ ATTR_LIST_SCHEMAS indicates a list of schemas in a database</li> </ul>

**Table 13–26 (Cont.) Enumerated Values Used by MetaData Class**

Attribute	Options
AttrId for Databases	<p data-bbox="602 260 1365 310">Parameter is for list of columns, arguments or subprograms (<a href="#">ParamType</a> of <a href="#">PTYPE_DATABASE</a>):</p> <ul style="list-style-type: none"> <li data-bbox="602 327 1143 352">■ <a href="#">ATTR_VERSION</a> indicates the database version</li> <li data-bbox="602 367 1333 392">■ <a href="#">ATTR_CHARSET_ID</a> indicates the character set ID of the database</li> <li data-bbox="602 407 1308 457">■ <a href="#">ATTR_NCHARSET_ID</a> indicates the national character set of the database</li> <li data-bbox="602 472 1289 522">■ <a href="#">ATTR_LIST_SCHEMAS</a> indicates the list of schemas, <a href="#">PTYPE_SCHEMA</a></li> <li data-bbox="602 537 1263 588">■ <a href="#">ATTR_MAX_PROC_LEN</a> indicates the maximum length of a procedure name</li> <li data-bbox="602 602 1292 653">■ <a href="#">ATTR_MAX_COLUMN_LEN</a> indicates the maximum length of a column name</li> <li data-bbox="602 667 1365 751">■ <a href="#">ATTR_CURSOR_COMMIT_BEHAVIOR</a> indicates how a commit affects cursors and prepared statements. Values can be <a href="#">CURSOR_OPEN</a> and <a href="#">CURSER_CLOSED</a>, as defined for attribute <a href="#">AttrValues</a></li> <li data-bbox="602 766 1365 816">■ <a href="#">ATTR_MAX_CATALOG_NAMELEN</a> indicates the maximum length of a database (catalog) name</li> <li data-bbox="602 831 1354 915">■ <a href="#">ATTR_CATALOG_LOCATION</a> indicates the position of the catalog in a qualified table. Values can be <a href="#">CL_START</a> and <a href="#">CL_END</a>, as defined for attribute <a href="#">AttrValues</a></li> <li data-bbox="602 930 1295 1014">■ <a href="#">ATTR_SAVEPOINT_SUPPORT</a> indicates whether the database supports savepoints. Values can be <a href="#">SP_SUPPORTED</a> and <a href="#">SP_UNSUPPORTED</a>, as defined for attribute <a href="#">AttrValues</a></li> <li data-bbox="602 1029 1354 1113">■ <a href="#">ATTR_NOWAIT_SUPPORT</a> indicates whether the database supports the "no wait" condition. Values can be <a href="#">NW_SUPPORTED</a> and <a href="#">NW_UNSUPPORTED</a>, as defined for attribute <a href="#">AttrValues</a></li> <li data-bbox="602 1127 1338 1211">■ <a href="#">ATTR_AUTOCOMMIT_DDL</a> indicates if an autocommit mode is required for DDL statements. Values can be <a href="#">AC_DDL</a> and <a href="#">NO_AC_DDL</a>, as defined for attribute <a href="#">AttrValues</a></li> <li data-bbox="602 1226 1360 1281">■ <a href="#">ATTR_LOCKING_MODE</a> indicates the locking mode for the database. Values can be <a href="#">LOCK_IMMEDIATE</a> and <a href="#">LOCK_DELAYED</a>, as defined for attribute <a href="#">AttrValues</a></li> </ul>

**Table 13–26 (Cont.) Enumerated Values Used by MetaData Class**

Attribute	Options
AttrValues	<p>Attribute values are returned on executing a <code>getxxx()</code> method and passing in an attribute, for which these are the results:</p> <ul style="list-style-type: none"> <li>■ <code>DURATION_SESSION</code> is the duration of a temporary table: session.</li> <li>■ <code>DURATION_TRANS</code> is the duration of a temporary table: transaction.</li> <li>■ <code>DURATION_NULL</code> is the duration of a temporary table: table not temporary.</li> <li>■ <code>TYPEENCAP_PRIVATE</code> is the encapsulation level of the method: private.</li> <li>■ <code>TYPEENCAP_PUBLIC</code> is the encapsulation level of the method: public.</li> <li>■ <code>TYPEPARAM_IN</code> is the argument mode: IN.</li> <li>■ <code>TYPEPARAM_OUT</code> is the argument mode: OUT.</li> <li>■ <code>TYPEPARAM_INOUT</code> is the argument mode: IN/OUT.</li> <li>■ <code>CURSOR_OPEN</code> is the effect of <code>COMMIT</code> operation on cursors and prepared statements in the database: preserve cursor state as before the <code>COMMIT</code> operation.</li> <li>■ <code>CURSER_CLOSED</code> is the effect of <code>COMMIT</code> operation on cursors and prepared statements in the database: cursors are closed on <code>COMMIT</code>, but the application can still rerun the statement without preparing it again.</li> <li>■ <code>CL_START</code> is the position of the catalog in a qualified table: start.</li> <li>■ <code>CL_END</code> is the position of the catalog in a qualified table: end.</li> <li>■ <code>SP_SUPPORTED</code> is the database supports savepoints.</li> <li>■ <code>SP_UNSUPPORTED</code> is the database does not support savepoints.</li> <li>■ <code>NW_SUPPORTED</code> is the database supports nowait clause.</li> <li>■ <code>NW_UNSUPPORTED</code> is the database does not supports nowait clause.</li> <li>■ <code>AC_DDL</code> is the autocommit mode required for DDL statements.</li> <li>■ <code>NO_AC_DDL</code> is the autocommit mode not required for DDL statements.</li> <li>■ <code>LOCK_IMMEDIATE</code> is the locking mode for the database: immediate.</li> <li>■ <code>LOCK_DELAYED</code> is the locking mode for the database: delayed.</li> </ul>

**Table 13–27 Summary of MetaData Methods**

Method	Description
<a href="#">MetaData()</a> on page 13-136	MetaData class constructor.
<a href="#">getAttributeCount()</a> on page 13-136	Gets the count of the attribute as a MetaData object
<a href="#">getAttributeId()</a> on page 13-136	Gets the ID of the specified attribute
<a href="#">getAttributeType()</a> on page 13-136	Gets the type of the specified attribute.
<a href="#">getBoolean()</a> on page 13-137	Gets the value of the attribute as a C++ <code>boolean</code> .
<a href="#">getInt()</a> on page 13-137	Gets the value of the attribute as a C++ <code>int</code> .
<a href="#">getMetaData()</a> on page 13-137	Gets the value of the attribute as a MetaData object
<a href="#">getNumber()</a> on page 13-138	Returns the specified attribute as a <code>Number</code> object.
<a href="#">getRef()</a> on page 13-138	Gets the value of the attribute as a <code>Ref&lt;T&gt;</code> .

**Table 13–27 (Cont.) Summary of MetaData Methods**

Method	Description
<a href="#">getString()</a> on page 13-138	Gets the value of the attribute as a string.
<a href="#">getTimeStamp()</a> on page 13-138	Gets the value of the attribute as a Timestamp object
<a href="#">getUInt()</a> on page 13-139	Gets the value of the attribute as a C++ unsigned int.
<a href="#">getUString()</a> on page 13-139	Returns the value of the attribute as a UString in the character set associated with the metadata.
<a href="#">getVector()</a> on page 13-139	Gets the value of the attribute as an C++ vector.
<a href="#">operator=()</a> on page 13-139	Assigns one metadata object to another.

## MetaData()

MetaData class constructor.

### Syntax

```
MetaData (
    const MetaData &cmd);
```

Parameter	Description
cmd	The source that the MetaData object will be copied from.

## getAttributeCount()

This method returns the number of attributes related to the metadata object.

### Syntax

```
unsigned int getAttributeCount() const;
```

## getAttributeId()

This method returns the attribute ID (ATTR\_NUM\_COLS, ...) of the attribute represented by the attribute number specified.

### Syntax

```
AttrId getAttributeId(
    unsigned int attributeNum) const;
```

Parameter	Description
attributeNum	The number of the attribute for which the attribute ID is to be returned.

## getAttributeType()

This method returns the attribute type (NUMBER, INT, ...) of the attribute represented by attribute number specified.



### Syntax

```
Type getAttributeType(
    unsigned int attributeNum) const;
```

Parameter	Description
attributeNum	The number of the attribute for which the attribute type is to be returned.

## getBoolean()

This method returns the value of the attribute as a C++ `boolean`. If the value is a SQL `NULL`, the result is `FALSE`.

### Syntax

```
bool getBoolean(
    MetaData::AttrId attributeId) const;
```

Parameter	Description
attributeId	The attribute ID

## getInt()

This method returns the value of the attribute as a C++ `int`. If the value is SQL `NULL`, the result is 0.

### Syntax

```
int getInt(
    MetaData::AttrId attributeId) const;
```

Parameter	Description
attributeId	The attribute ID

## getMetaData()

This method returns a `MetaData` instance holding the attribute value. A metadata attribute value can be retrieved as a `MetaData` instance. This method can only be called on attributes of the metadata type.

### Syntax

```
MetaData getMetaData(
    MetaData::AttrId attributeId) const;
```

Parameter	Description
attributeId	The attribute ID

## getNumber()

This method returns the value of the attribute as a `Number` object. If the value is a SQL `NULL`, the result is `NULL`.

### Syntax

```
Number getNumber(  
    MetaData::AttrId attributeId) const;
```

Parameter	Description
attributeId	The attribute ID

## getRef()

This method returns the value of the attribute as a `RefAny`, or `Ref` to a `TDO`. If the value is SQL `NULL`, the result is `NULL`.

### Syntax

```
RefAny getRef(  
    MetaData::AttrId attributeId) const;
```

Parameter	Description
attributeId	The attribute ID

## getString()

This method returns the value of the attribute as a string. If the value is SQL `NULL`, the result is `NULL`.

### Syntax

```
string getString(  
    MetaData::AttrId attributeId) const;
```

Parameter	Description
attributeId	The attribute ID

## getTimeStamp()

This method returns the value of the attribute as a `TimeStamp` object. If the value is a SQL `NULL`, the result is `NULL`.

### Syntax

```
TimeStamp getTimeStamp(  
    MetaData::AttrId attributeId) const;
```

Parameter	Description
attributeId	The attribute ID

## getUInt()

This method returns the value of the attribute as a C++ unsigned `int`. If the value is a SQL `NULL`, the result is 0.

### Syntax

```
unsigned int getUInt(
    MetaData::AttrId attributeId) const;
```

Parameter	Description
attributeId	The attribute ID

## getUString()

Returns the value of an attribute as a `UString` in the character set associated with the metadata.

### Syntax

```
UString getUString(
    MetaData::AttrId attributeId) const;
```

Parameter	Description
attributeId	The attribute ID

## getVector()

This method returns a C++ vector containing the attribute value. A collection attribute value can be retrieved as a C++ vector instance. This method can only be called on attributes of a list type.

### Syntax

```
vector<MetaData> getVector(
    MetaData::AttrId attributeId) const;
```

Parameter	Description
attributeId	The attribute ID

## operator=()

This method assigns one `MetaData` object to another. This increments the reference count of the `MetaData` object that is assigned.

## Syntax

```
void operator=(  
    const MetaData &omd);
```

Parameter	Description
cmd	MetaData object to be assigned

---

## NotifyResult Class

A NotifyResult object holds the notification information in the Streams AQ notification callback. It is created by OCCI before invoking a user-callback, and is destroyed after the user-callback returns.

**Table 13–28 Summary of NotifyResult Methods**

Method	Summary
<a href="#">getConsumerName()</a> on page 13-141	Returns the name of the notification consumer.
<a href="#">getMessage()</a> on page 13-141	Returns the message.
<a href="#">getMessageId()</a> on page 13-141	Returns the message ID.
<a href="#">getPayload()</a> on page 13-141	Returns the payload.
<a href="#">getQueueName()</a> on page 13-141	Returns the name of the queue.

### getConsumerName()

Gets the name of the consumer for which the message has been enqueued. In case of a single consumer queue, this is an empty string.

```
string getConsumerName() const;
```

### getMessage()

Gets the message which has been enqueued into the non-persistent queue.

```
Message getMessage() const;
```

### getMessageId()

Gets the id of the message which has been enqueued.

```
Bytes getMessageId() const;
```

### getPayload()

Gets the payload in case of a notification from NS\_ANONYMOUS namespace.

```
Bytes getPayload() const;
```

### getQueueName()

Gets the name of the queue on which the enqueue has happened

```
string getQueueName() const;
```



```

/* Some common Number methods */
Number abs = nul.abs();    /* absolute value */
Number sqrt = nul.squareroot();    /* square root */
Environment *env = Environment::createEnvironment();

//create a null year-month interval
IntervalYM ym
if(ym.isNull())
    cout << "\n ym is null";

//assign a non null value to ym
IntervalYM anotherYM(env, "10-30");
ym = anotherYM;

//now all operations are valid on ym
int yr = ym.getYear();

```

**Table 13–29 Summary of Number Methods**

Method	Summary
<a href="#">Number()</a> on page 13-145	Number class constructor.
<a href="#">abs()</a> on page 13-146	Returns the absolute value of the number.
<a href="#">arcCos()</a> on page 13-146	Returns the arcCosine of the number.
<a href="#">arcSin()</a> on page 13-146	Returns the arcSine of the number.
<a href="#">arcTan()</a> on page 13-146	Returns the arcTangent of the number.
<a href="#">arcTan2()</a> on page 13-147	Returns the arcTangent2 of the input number <i>y</i> and this number <i>x</i> .
<a href="#">ceil()</a> on page 13-147	Returns the smallest integral value not less than the value of the number.
<a href="#">cos()</a> on page 13-147	Returns the cosine of the number.
<a href="#">exp()</a> on page 13-147	Returns the natural exponent of the number.
<a href="#">floor()</a> on page 13-147	Returns the largest integral value not greater than the value of the number.
<a href="#">fromBytes()</a> on page 13-147	Returns a Number derived from a Bytes object.
<a href="#">fromText()</a> on page 13-148	Returns a Number from a given number string, format string and NLS parameters specified.
<a href="#">hypCos()</a> on page 13-148	Returns the hyperbolic cosine of the number.
<a href="#">hypSin()</a> on page 13-149	Returns the hyperbolic sine of the number.
<a href="#">hypTan()</a> on page 13-149	Returns the hyperbolic tangent of the number.
<a href="#">intPower()</a> on page 13-149	Returns the number raised to the integer value specified.
<a href="#">isNull()</a> on page 13-149	Checks if Number is NULL.
<a href="#">ln()</a> on page 13-149	Returns the natural logarithm of the number.
<a href="#">log()</a> on page 13-149	Returns the logarithm of the number to the base value specified.
<a href="#">operator++()</a> on page 13-150	Increments the number.
<a href="#">operator--()</a> on page 13-150	Decrements the number.
<a href="#">operator*()</a> on page 13-101	Returns the product of two Numbers.

**Table 13–29 (Cont.) Summary of Number Methods**

<b>Method</b>	<b>Summary</b>
<a href="#">operator/()</a> on page 13-151	Returns the quotient of two Numbers.
<a href="#">operator%()</a> on page 13-151	Returns the modulo of two Numbers.
<a href="#">operator+()</a> on page 13-151	Returns the sum of two Numbers.
<a href="#">operator-()</a> on page 13-151	Returns the negated value of Number .
<a href="#">operator-()</a> on page 13-151	Returns the difference between two Numbers.
<a href="#">operator&lt;()</a> on page 13-152	Checks if a number is less than an other number.
<a href="#">operator&lt;=()</a> on page 13-152	Checks if a number is less than or equal to an other number.
<a href="#">operator&gt;()</a> on page 13-153	Checks if a number is greater than an other number.
<a href="#">operator&gt;=()</a> on page 13-81	Checks if a number is greater than or equal to an other number.
<a href="#">operator=()</a> on page 13-80	Assigns one number to another.
<a href="#">operator==(())</a> on page 13-80	Checks if two numbers are equal.
<a href="#">operator!=(())</a> on page 13-80	Checks if two numbers are not equal.
<a href="#">operator*=(())</a> on page 13-101	Multiplication assignment.
<a href="#">operator/=(())</a> on page 13-103	Division assignment.
<a href="#">operator%=(())</a> on page 13-155	Modulo assignment.
<a href="#">operator+=(())</a> on page 13-155	Addition assignment.
<a href="#">operator-=(())</a> on page 13-155	Subtraction assignment.
<a href="#">operator char()</a> on page 13-155	Returns Number converted to native char.
<a href="#">operator signed char()</a> on page 13-156	Returns Number converted to native signed char.
<a href="#">operator double()</a> on page 13-156	Returns Number converted to a native double.
<a href="#">operator float()</a> on page 13-156	Returns Number converted to a native float.
<a href="#">operator int()</a> on page 13-156	Returns Number converted to native integer.
<a href="#">operator long()</a> on page 13-156	Returns Number converted to native long.
<a href="#">operator long double()</a> on page 13-156	Returns Number converted to a native long double.
<a href="#">operator short()</a> on page 13-157	Returns Number converted to native short integer.
<a href="#">operator unsigned char()</a> on page 13-157	Returns Number converted to an unsigned native char.
<a href="#">operator unsigned int()</a> on page 13-157	Returns Number converted to an unsigned native integer.
<a href="#">operator unsigned long()</a> on page 13-157	Returns Number converted to an unsigned native long.
<a href="#">operator unsigned short()</a> on page 13-157	Returns Number converted to an unsigned native short integer.
<a href="#">power()</a> on page 13-157	Returns Number raised to the power of another number specified.
<a href="#">prec()</a> on page 13-158	Returns Number rounded to digits of precision specified.



**Table 13–29 (Cont.) Summary of Number Methods**

Method	Summary
<a href="#">round()</a> on page 13-158	Returns <code>Number</code> rounded to decimal place specified. Negative values are allowed.
<a href="#">setNull()</a> on page 13-158	Sets <code>Number</code> to <code>NULL</code> .
<a href="#">shift()</a> on page 13-158	Returns a <code>Number</code> that is equivalent to the passed value * $10^n$ , where $n$ may be positive or negative.
<a href="#">sign()</a> on page 13-159	Returns the sign of the value of the passed value: -1 for the passed value < 0, 0 for the passed value == 0, and 1 for the passed value > 0.
<a href="#">sin()</a> on page 13-159	Returns sine of the number.
<a href="#">sqrareeroot()</a> on page 13-159	Returns the square root of the number.
<a href="#">tan()</a> on page 13-159	Returns tangent of the number.
<a href="#">toBytes()</a> on page 13-159	Returns a <code>Bytes</code> object representing the <code>Number</code> .
<a href="#">toText()</a> on page 13-159	Returns the number as a string formatted based on the format and NLS parameters.
<a href="#">trunc()</a> on page 13-160	Returns a <code>Number</code> with the value truncated at $n$ decimal place(s). Negative values are allowed.

## Number()

`Number` class constructor.

Syntax	Description
<code>Number ();</code>	Default constructor.
<code>Number (const Number &amp;srcNum);</code>	Creates a copy of a <code>Number</code> .
<code>Number (long double &amp;val);</code>	Translates a native long double into a <code>Number</code> . The <code>Number</code> is created using the precision of the platform-specific constant <code>LDBL_DIG</code> .
<code>Number (double val);</code>	Translates a native double into a <code>Number</code> . The <code>Number</code> is created using the precision of the platform-specific constant <code>DBL_DIG</code> .
<code>Number (float val);</code>	Translates a native float into a <code>Number</code> . The <code>Number</code> is created using the precision of the platform-specific constant <code>FLT_DIG</code> .
<code>Number (long val);</code>	Translates a native long into a <code>Number</code> .
<code>Number (int val);</code>	Translates a native int into a <code>Number</code> .
<code>Number (short val);</code>	Translates a native short into a <code>Number</code> .
<code>Number (char val);</code>	Translates a native char into a <code>Number</code> .
<code>Number (signed char val);</code>	Translates a native signed char into a <code>Number</code> .

Syntax	Description
<code>Number ( unsigned long val);</code>	Translates an native unsigned long into a <code>Number</code> .
<code>Number ( unsigned int val);</code>	Translates a native unsigned int into a <code>Number</code> .
<code>Number ( unsigned short val);</code>	Translates a native unsigned short into a <code>Number</code> .
<code>Number ( unsigned char val);</code>	Translates the unsigned character array into a <code>Number</code> .

Parameter	Description
<code>srcNum</code>	The source <code>Number</code> copied into the new <code>Number</code> object.
<code>val</code>	The value assigned to the <code>Number</code> object.

## abs()

This method returns the absolute value of the `Number` object.

### Syntax

```
const Number abs() const;
```

## arcCos()

This method returns the arccosine of the `Number` object.

### Syntax

```
const Number arcCos() const;
```

## arcSin()

This method returns the arcsine of the `Number` object.

### Syntax

```
const Number arcSin() const;
```

## arcTan()

This method returns the arctangent of the `Number` object.

### Syntax

```
const Number arcTan() const;
```

## arcTan2()

This method returns the arctangent of the `Number` object with the parameter specified. It returns `atan2 (val, x)` where `val` is the parameter specified and `x` is the current number object.

### Syntax

```
const Number arcTan2(
    const Number &val) const;
```

Parameter	Description
<code>val</code>	Number parameter <code>val</code> to the arcTangent function <code>atan2 (val, x)</code> .

## ceil()

This method returns the smallest integer that is greater than or equal to the `Number` object.

### Syntax

```
const Number ceil() const;
```

## cos()

This method returns the cosine of the `Number` object.

### Syntax

```
const Number cos() const;
```

## exp()

This method returns the natural exponential of the `Number` object.

### Syntax

```
const Number exp() const;
```

## floor()

This method returns the largest integer that is less than or equal to the `Number` object.

### Syntax

```
const Number floor() const;
```

## fromBytes()

This method returns a `Number` object represented by the byte string specified.

**Syntax**

```
void fromBytes(
    const Bytes &str);
```

Parameter	Description
str	A byte string.

**fromText()**

Sets `Number` object to value represented by a `string` or `UString`.

The value is interpreted based on the `fmt` and `nlsParam` parameters. In cases where `nlsParam` is not passed, the Globalization Support settings of the `envp` parameter are used.

**See Also:** *Oracle Database SQL Language Reference* for information on `TO_NUMBER`

Syntax	Description
<pre>void fromText(     const Environment *envp,     const string &amp;number,     const string &amp;fmt,     const string &amp;nlsParam = "");</pre>	Sets <code>Number</code> object to value represented by a <code>string</code> .
<pre>void fromText(     const Environment *envp,     const UString &amp;number,     const UString &amp;fmt,     const UString &amp;nlsParam);</pre>	Sets <code>Number</code> object to value represented by a <code>UString</code> .

Parameter	Description
envp	The OCI environment.
number	The number string to be converted to a <code>Number</code> object.
fmt	The format string.
nlsParam	The NLS parameters string. If <code>nlsParam</code> is specified, this determines the NLS parameters to be used for the conversion. If <code>nlsParam</code> is not specified, the NLS parameters are picked up from <code>envp</code> .

**hypCos()**

This method returns the hypercosine of the `Number` object.

**Syntax**

```
const Number hypCos() const;
```

## hypSin()

This method returns the hypersine of the `Number` object.

### Syntax

```
const Number hypSin() const;
```

## hypTan()

This method returns the hypertangent of the `Number` object.

### Syntax

```
const Number hypTan() const;
```

## intPower()

This method returns a `Number` whose value is the number object raised to the power of the value specified.

### Syntax

```
const Number intPower(  
    int val) const;
```

Parameter	Description
<code>val</code>	Power to which the number is raised.

## isNull()

This method tests whether the `Number` object is `NULL`. If the `Number` object is `NULL`, then `TRUE` is returned; otherwise, `FALSE` is returned.

### Syntax

```
bool isNull() const;
```

## ln()

This method returns the natural logarithm of the `Number` object.

### Syntax

```
const Number ln() const;
```

## log()

This method returns the logarithm of the `Number` object with the base provided by the parameter specified.

**Syntax**

```
const Number log(
    const Number &val) const;
```

Parameter	Description
val	The base to be used in the logarithm calculation.

**operator++()**

Unary operator++(). This is a postfix operator.

Syntax	Description
Number& operator++();	This method returns the Number object incremented by 1.
const Number operator++(     int incr);	This method returns the Number object incremented by the integer specified.

Parameter	Description
incr	The number by which the Number object is incremented.

**operator--()**

Unary operator--(). This is a prefix operator.

Syntax	Description
Number& operator--();	This method returns the Number object decremented by 1.
const Number operator--(     int decr);	This method returns the Number object decremented by the integer specified.

Parameter	Description
decr	The number by which the Number object is decremented.

**operator\*()**

This method returns the product of the parameters specified.

**Syntax**

```
Number operator*(
    const Number &first,
    const Number &second);
```

Parameter	Description
first	First multiplicand.

Parameter	Description
second	Second multiplicand.

## operator/()

This method returns the quotient of the parameters specified.

### Syntax

```
Number operator/(
    const Number &dividend,
    const Number &divisor);
```

Parameter	Description
dividend	The number to be divided.
divisor	The number by which to divide.

## operator%()

This method returns the remainder of the division of the parameters specified.

### Syntax

```
Number operator%(
    const Number &dividend,
    const Number &divisor);
```

Parameter	Description
dividend	The number to be divided.
divisor	The number by which to divide.

## operator+()

This method returns the sum of the parameters specified.

### Syntax

```
Number operator+(
    const Number &first,
    const Number &second);
```

Parameter	Description
first	First number to be added.
second	Second number to be added.

## operator-()

Unary operator- (). This method returns the negated value of the `Number` object.

**Syntax**

```
const Number operator-();
```

**operator-()**

This method returns the difference between the parameters specified.

**Syntax**

```
Number operator-(
    const Number &subtrahend,
    const Number &subtractor);
```

Parameter	Description
subtrahend	The number to be reduced.
subtractor	The number to be subtracted.

**operator<()**

This method checks whether the first parameter specified is less than the second parameter specified. If the first parameter is less than the second parameter, then `TRUE` is returned; otherwise, `FALSE` is returned. If either parameter is equal to infinity, then `FALSE` is returned.

**Syntax**

```
bool operator<(
    const Number &first,
    const Number &second);
```

Parameter	Description
first	First number to be compared.
second	Second number to be compared.

**operator<=()**

This method checks whether the first parameter specified is less than or equal to the second parameter specified. If the first parameter is less than or equal to the second parameter, then `TRUE` is returned; otherwise, `FALSE` is returned. If either parameter is equal to infinity, then `FALSE` is returned.

**Syntax**

```
bool operator<=(
    const Number &first,
    const Number &second);
```

Parameter	Description
first	First number to be compared.
second	Second number to be compared.



## operator>()

This method checks whether the first parameter specified is greater than the second parameter specified. If the first parameter is greater than the second parameter, then `TRUE` is returned; otherwise, `FALSE` is returned. If either parameter is equal to infinity, then `FALSE` is returned.

### Syntax

```
bool operator>(
    const Number &first,
    const Number &second);
```

Parameter	Description
first	First number to be compared.
second	Second number to be compared.

## operator>=()

This method checks whether the first parameter specified is greater than or equal to the second parameter specified. If the first parameter is greater than or equal to the second parameter, then `TRUE` is returned; otherwise, `FALSE` is returned. If either parameter is equal to infinity, then `FALSE` is returned.

### Syntax

```
bool operator>=(
    const Number &first,
    const Number &second);
```

Parameter	Description
first	First number to be compared.
second	Second number to be compared.

## operator==(())

This method checks whether the parameters specified are equal. If the parameters are equal, then `TRUE` is returned; otherwise, `FALSE` is returned. If either parameter is equal to +infinity or -infinity, then `FALSE` is returned.

### Syntax

```
bool operator==(
    const Number &first,
    const Number &second);
```

Parameter	Description
first	First number to be compared.
second	Second number to be compared.

## operator!==( )

This method checks whether the first parameter specified is equal to the second parameter specified. If the parameters are not equal, `TRUE` is returned; otherwise, `FALSE` is returned.

### Syntax

```
bool operator!=(  
    const Number &first,  
    const Number &second);
```

Parameter	Description
<code>first</code>	First number to be compared.
<code>second</code>	Second number to be compared.

## operator==( )

This method assigns the value of the parameter specified to the `Number` object.

### Syntax

```
Number& operator=(  
    const Number &num);
```

Parameter	Description
<code>num</code>	A parameter of type <code>Number</code> .

## operator\*==( )

This method multiplies the `Number` object by the parameter specified, and assigns the product to the `Number` object.

### Syntax

```
Number& operator*=(  
    const Number &num);
```

Parameter	Description
<code>num</code>	A parameter of type <code>Number</code> .

## operator/==( )

This method divides the `Number` object by the parameter specified, and assigns the quotient to the `Number` object.

### Syntax

```
Number& operator/=(  
    const Number &num);
```

Parameter	Description
num	A parameter of type <code>Number</code> .

## operator%=( )

This method divides the `Number` object by the parameter specified, and assigns the remainder to the `Number` object.

### Syntax

```
Number& operator%=(
    const Number &num);
```

Parameter	Description
num	A parameter of type <code>Number</code> .

## operator+=( )

This method adds the `Number` object and the parameter specified, and assigns the sum to the `Number` object.

### Syntax

```
Number& operator+=(
    const Number &num);
```

Parameter	Description
num	A parameter of type <code>Number</code> .

## operator-=( )

This method subtracts the parameter specified from the `Number` object, and assigns the difference to the `Number` object.

### Syntax

```
Number& operator-=(
    const Number &num);
```

Parameter	Description
num	A parameter of type <code>Number</code> .

## operator char( )

This method returns the value of the `Number` object converted to a native `char`.

### Syntax

```
operator char() const;
```

## operator signed char()

This method returns the value of the `Number` object converted to a native `signed char`.

### Syntax

```
operator signed char() const;
```

## operator double()

This method returns the value of the `Number` object converted to a native `double`.

### Syntax

```
operator double() const;
```

## operator float()

This method returns the value of the `Number` object converted to a native `float`.

### Syntax

```
operator float() const;
```

## operator int()

This method returns the value of the `Number` object converted to a native `int`.

### Syntax

```
operator int() const;
```

## operator long()

This method returns the value of the `Number` object converted to a native `long`.

### Syntax

```
operator long() const;
```

## operator long double()

This method returns the value of the `Number` object converted to a native `long double`.

### Syntax

```
operator long double() const;
```

## operator short()

This method returns the value of the `Number` object converted to a native `short` integer.

### Syntax

```
operator short() const;
```

## operator unsigned char()

This method returns the value of the `Number` object converted to a native unsigned `char`.

### Syntax

```
operator unsigned char() const;
```

## operator unsigned int()

This method returns the value of the `Number` object converted to a native unsigned `int`.

### Syntax

```
operator unsigned int() const;
```

## operator unsigned long()

This method returns the value of the `Number` object converted to a native unsigned `long`.

### Syntax

```
operator unsigned long() const;
```

## operator unsigned short()

This method returns the value of the `Number` object converted to a native unsigned `short` integer.

### Syntax

```
operator unsigned short() const;
```

## power()

This method returns the value of the `Number` object raised to the power of the value provided by the parameter specified.

### Syntax

```
const Number power(  
    const Number &val) const;
```

prec()

---

Parameter	Description
val	The power to which the number has to be raised.

## prec()

This method returns the value of the `Number` object rounded to the digits of precision provided by the parameter specified.

### Syntax

```
const Number prec(  
    int digits) const;
```

Parameter	Description
digits	The number of digits of precision.

## round()

This method returns the value of the `Number` object rounded to the decimal place provided by the parameter specified.

### Syntax

```
const Number round(  
    int decPlace) const;
```

Parameter	Description
decPlace	The number of digits to the right of the decimal point.

## setNull()

This method sets the value of the `Number` object to `NULL`.

### Syntax

```
void setNull();
```

## shift()

This method returns the `Number` object multiplied by 10 to the power provided by the parameter specified.

### Syntax

```
const Number shift(  
    int val) const;
```

Parameter	Description
val	An integer value.

## sign()

This method returns the sign of the value of the `Number` object. If the `Number` object is negative, then `-1` is returned. If the `Number` object is equal to `0`, then `0` is returned. If the `Number` object is positive, then `1` is returned.

### Syntax

```
const int sign() const;
```

## sin()

This method returns the sin of the `Number` object.

### Syntax

```
const Number sin() const;
```

## squareroot()

This method returns the square root of the `Number` object.

### Syntax

```
const Number squareroot() const;
```

## tan()

This method returns the tangent of the `Number` object.

### Syntax

```
const Number tan() const;
```

## toBytes()

This method converts the `Number` object into a `Bytes` object. The bytes representation is assumed to be in length excluded format, that is, the `Byte.length()` method gives the length of valid bytes and the 0th byte is the exponent byte.

### Syntax

```
Bytes toBytes() const;
```

## toText()

Convert the `Number` object to a formatted `string` or `UString` based on the parameters specified.

**See Also:** *Oracle Database SQL Language Reference* for information on `TO_NUMBER`

Syntax	Description
<pre>string toText(     const Environment *envp,     const string &amp;fmt,     const string &amp;nlsParam = "") const;</pre>	Convert the <code>Number</code> object to a formatted string based on the parameters specified.
<pre>UString toText(     const Environment *envp,     const UString &amp;fmt,     const UString &amp;nlsParam) const;</pre>	Convert the <code>Number</code> object to a <code>UString</code> based on the parameters specified.

Parameter	Description
<code>envp</code>	The OCCI environment.
<code>fmt</code>	The format string.
<code>nlsParam</code>	The NLS parameters string. If <code>nlsParam</code> is specified, this determines the NLS parameters to be used for the conversion. If <code>nlsParam</code> is not specified, the NLS parameters are picked up from <code>envp</code> .

## trunc()

This method returns the `Number` object truncated at the number of decimal places provided by the parameter specified.

### Syntax

```
const Number trunc(
    int decPlace) const;
```

Parameter	Description
<code>decPlace</code>	The number of places to the right of the decimal place at which the value is to be truncated.



## PObject Class

OCCI provides object navigational calls that enable applications to perform any of the following on objects:

- Creating, accessing, locking, deleting, copying, and flushing objects
- Getting references to the objects

This class enables the type definer to specify when a class is capable of having persistent or transient instances. Instances of classes derived from `PObject` are either persistent or transient. A class (called "A") that is persistent-capable inherits from the `PObject` class:

```
class A : PObject { ... }
```

The only methods valid on a `NULL PObject` are `setName()`, `isNull()`, and `operator=()`.

Some of the methods provided, such as `lock()`, apply only for persistent instances, not for transient instances.

**Table 13–30 Enumerated Values Used by PObject Class**

Attribute	Options
LockOption	<ul style="list-style-type: none"> <li>■ <code>OCCI_LOCK_WAIT</code> instructs the cache to pin the object only after acquiring a lock; if the object is locked by another user, the pin call with this option will wait until it can acquire the lock before returning to the caller; equivalent to <code>SELECT FOR UPDATE</code></li> <li>■ <code>OCCI_LOCK_NOWAIT</code> instructs the cache to pin the object only after acquiring a lock; will not wait if the object is currently locked by another user; equivalent to <code>SELECT FOR UPDATE WITH NOWAIT</code></li> </ul>
UnpinOption	<ul style="list-style-type: none"> <li>■ <code>OCCI_PINCOUNT_RESET</code> resets the object's pin count to 0</li> <li>■ <code>OCCI_PINCOUNT_DECR</code> decrements the object's pin count by 1</li> </ul>

**Table 13–31 Summary of PObject Methods**

Method	Summary
<code>PObject()</code> on page 13-162	<code>PObject</code> class constructor.
<code>flush()</code> on page 13-162	Flushes a modified persistent object to the database server.
<code>getConnection()</code> on page 13-162	Returns the connection from which the <code>PObject</code> object was instantiated.
<code>getRef()</code> on page 13-162	Returns a reference to a given persistent object.
<code>getSQLTypeName()</code> on page 13-163	Returns the Oracle database typename for this class.
<code>isLocked()</code> on page 13-163	Tests whether the persistent object is locked.
<code>isNull()</code> on page 13-163	Tests whether the object is <code>NULL</code> .
<code>lock()</code> on page 13-163	Lock a persistent object on the database server. The default mode is to wait for the lock if not available.
<code>markDelete()</code> on page 13-163	Marks a persistent object as deleted.
<code>markModified()</code> on page 13-163	Marks a persistent object as modified or dirty.
<code>operator=()</code> on page 13-164	Assigns one <code>PObject</code> to another.

**Table 13–31 (Cont.) Summary of PObject Methods**

Method	Summary
<a href="#">operator delete()</a> on page 13-164	Remove the persistent object from the application cache only.
<a href="#">operator new()</a> on page 13-164	Creates a new persistent / transient instance.
<a href="#">pin()</a> on page 13-165	Pins an object.
<a href="#">setNull()</a> on page 13-165	Sets the object value to NULL.
<a href="#">unmark()</a> on page 13-165	Unmarks an object as dirty.
<a href="#">unpin()</a> on page 13-165	Unpins an object. In the default mode, the pin count of the object is decremented by one.

## PObject()

PObject class constructor.

Syntax	Description
<code>PObject();</code>	Creates a NULL PObject.
<code>PObject(   const PObject &amp;obj);</code>	Creates a copy of PObject.

Parameter	Description
<code>obj</code>	The source object.

## flush()

This method flushes a modified persistent object to the database server.

### Syntax

```
void flush();
```

## getConnection()

Returns the connection from which the persistent object was instantiated.

### Syntax

```
const Connection *getConnection() const;
```

## getRef()

This method returns a reference to the persistent object.

### Syntax

```
RefAny getRef() const;
```

## getSQLTypeName()

Returns the Oracle database typename for this class.

### Syntax

```
string getSQLTypeName() const;
```

## isLocked()

This method test whether the persistent object is locked. If the persistent object is locked, then `TRUE` is returned; otherwise, `FALSE` is returned.

### Syntax

```
bool isLocked() const;
```

## isNull()

This method tests whether the persistent object is `NULL`. If the persistent object is `NULL`, then `TRUE` is returned; otherwise, `FALSE` is returned.

### Syntax

```
bool isNull() const;
```

## lock()

Locks a persistent object on the database server.

### Syntax

```
void lock(  
    PObject::LockOption lock_option);
```

Parameter	Description
<code>lock_option</code>	Locking options; see <a href="#">Table 13-30</a> .

## markDelete()

This method marks a persistent object as deleted.

### Syntax

```
void markDelete();
```

## markModified()

This method marks a persistent object as modified or dirty.

### Syntax

```
void mark_Modified();
```

## operator=()

This method assigns the value of a persistent object this `PObject` object. The nature (transient or persistent) of the object is maintained. `NULL` information is copied from the source instance.

### Syntax

```
PObject& operator=(
    const PObject& obj);
```

Parameter	Description
obj	The object from which the assigned value is obtained.

## operator delete()

Deletes a persistent or transient object. The delete operator on a persistent object removes the object from the application cache only. To delete the object from the database server, invoke the [markDelete\(\)](#) method.

### Syntax

```
void operator delete(
    void *obj,
    size_t size);
```

Parameter	Description
obj	The pointer to object to be deleted
size	(Optional) Size is implicitly obtained from the object

## operator new()

This method is used to create a new object. A persistent object is created if the connection and table name are provided. Otherwise, a transient object is created.

Syntax	Description
<pre>void *operator new(     size_t size);</pre>	Creates a default new object, with a size specification only
<pre>void *operator new(     size_t size,     const Connection *conn,     const string&amp; tableName,     const char *typeName);</pre>	Used for creating transient objects when client side character set is multibyte.
<pre>void *operator new(     size_t size,     const Connection *conn,     const string&amp; tableName,     const string&amp; typeName,     const string&amp; schTableName="",     const string&amp; schTypeName="");</pre>	Used for creating persistent objects when client side character set is multibyte.

Syntax	Description
<pre>void *operator new(     size_t size,     const Connection *conn,     const UString&amp; tableName,     const UString&amp; typeName,     const UString&amp; schTableName=" ",     const UString&amp; schTypeName=" ");</pre>	Used for creating persistent objects when client side charset is unicode (UTF16).

Parameter	Description
size	size of the object
conn	The connection to the database in which the persistent object is to be created.
tableName	The name of the table in the database server.
typeName	The SQL type name corresponding to this C++ class. The format is <i>&lt;schename&gt;.&lt;typename&gt;</i> .
schTableName	The schema table name.
schTypeName	The schema type name.

## pin()

This method pins the object and increments the pin count by one. As long as the object is pinned, it will not be freed by the cache even if there are no references to this object instance.

### Syntax

```
void pin();
```

## setNull()

This method sets the object value to NULL.

### Syntax

```
void setNull();
```

## unmark()

This method unmarks a persistent object as modified or deleted.

### Syntax

```
void unmark();
```

## unpin()

This method unpins a persistent object. In the default mode, the pin count of the object is decremented by one. When this method is invoked with `OCCI_PINCOUNT_RESET`, the pin count of the object is reset. If the pin count is reset, this method invalidates all

the references (Refs) pointing to this object. The cache sets the object eligible to be freed, if necessary, reclaiming memory.

### Syntax

```
void unpin(  
    UnpinOption mode=OCCI_PINCOUNT_DECR);
```

Parameter	Description
mode	Specifies whether the <code>UnpinOption</code> mode, or the pin count, should be decremented or reset to 0. See <a href="#">Table 13–30</a> . Valid values are <code>OCCI_PINCOUNT_RESET</code> and <code>OCCI_PINCOUNT_DECR</code> .

## Producer Class

The `Producer` enqueues `Messages` into a queue and defines the enqueue options.

**Table 13–32 Enumerated Values Used by Producer Class**

Attribute	Options
<code>EnqueueSequence</code>	<ul style="list-style-type: none"> <li>▪ <code>ENQ_BEFORE</code> indicates that the message is enqueued before the message specified by the related message id.</li> <li>▪ <code>ENQ_TOP</code> indicates that the message is enqueued before any other messages.</li> </ul>
<code>Visibility</code>	<ul style="list-style-type: none"> <li>▪ <code>ENQ_IMMEDIATE</code> indicates that the enqueue is not part of the current transaction. The operation constitutes a transaction of its own.</li> <li>▪ <code>ENQ_ON_COMMIT</code> indicates that the enqueue is part of the current transaction. The operation is complete when the transaction commits. This is the default setting.</li> </ul>

**Table 13–33 Summary of Producer Methods**

Method	Summary
<a href="#">Producer()</a> on page 13-168	<code>Producer</code> class constructor.
<a href="#">getQueueName()</a> on page 13-168	Retrieves the name of a queue on which the <code>Messages</code> will be enqueued.
<a href="#">getRelativeMessageId()</a> on page 13-168	Retrieves the <code>Message</code> id that is referenced in a sequence deviation operation.
<a href="#">getSequenceDeviation()</a> on page 13-168	Retrieves information regarding whether the <code>Message</code> should be dequeued ahead of other <code>Messages</code> in the queue.
<a href="#">getTransformation()</a> on page 13-168	Retrieves the transformation applied before a <code>Message</code> is enqueued.
<a href="#">getVisibility()</a> on page 13-169	Retrieves the transactional behavior of the enqueue request.
<a href="#">isNull()</a> on page 13-169	Tests whether the <code>Producer</code> is <code>NULL</code> .
<a href="#">send()</a> on page 13-169	Enqueues and sends a <code>Message</code> .
<a href="#">operator=()</a> on page 13-169	Assignment operator for <code>Producer</code> .
<a href="#">setNull()</a> on page 13-170	Frees memory if the scope of the <code>Producer</code> extends beyond the <code>Connection</code> on which it was created.
<a href="#">setQueueName()</a> on page 13-170	Specifies the name of a queue on which the <code>Messages</code> will be enqueued.
<a href="#">setRelativeMessageId()</a> on page 13-170	Specifies the <code>Message</code> id to be referenced in the sequence deviation operation.
<a href="#">setSequenceDeviation()</a> on page 13-170	Specifies whether <code>Message</code> should be dequeued before other <code>Messages</code> already in the queue.
<a href="#">setTransformation()</a> on page 13-171	Specifies transformation applied before enqueueing a <code>Message</code> .
<a href="#">setVisibility()</a> on page 13-171	Specifies transaction behavior of the enqueue request.

## Producer()

Producer object constructor.

Syntax	Description
<pre>Producer(     const Connection *conn);</pre>	Creates a <code>Producer</code> object with the specified <code>Connection</code> .
<pre>Producer(     const Connection *conn,     const string&amp; queue);</pre>	Creates a <code>Producer</code> object with the specified <code>Connection</code> and queue name.

Parameter	Description
<code>conn</code>	The connection of the new <code>Producer</code> object.
<code>queue</code>	The queue that will be used by the new <code>Producer</code> object.

## getQueueName()

Retrieves the name of a queue on which the `Messages` will be enqueued.

### Syntax

```
string getQueueName() const;
```

## getRelativeMessageId()

Retrieves the `Message` id that is referenced in a sequence deviation operation. Used only if a sequence deviation is specified; ignored otherwise.

### Syntax

```
Bytes getRelativeMessageId() const;
```

## getSequenceDeviation()

Retrieves information regarding whether the `Message` should be dequeued ahead of other `Messages` in the queue. Valid return values are `ENQ_BEFORE` and `ENQ_TOP`, as defined in [Table 13-32](#) on page 13-167.

### Syntax

```
EnqueueSequence getSequenceDeviation() const;
```

## getTransformation()

Retrieves the transformation applied before a `Message` is enqueued.

### Syntax

```
string getTransformation() const;
```



## getVisibility()

Retrieves the transactional behavior of the enqueue request. `Visibility` is defined in [Table 13–32](#) on page 13-167.

### Syntax

```
Visibility getVisibility() const;
```

## isNull()

Tests whether the `Producer` is `NULL`. If the `Producer` is `NULL`, then `TRUE` is returned; otherwise, `FALSE` is returned.

### Syntax

```
bool isNull() const;
```

## operator=()

The assignment operator for `Producer`.

### Syntax

```
void operator=(
    const Producer& prod);
```

Parameter	Description
<code>prod</code>	The original <code>Producer</code>

## send()

Enqueues and sends a `Message`.

Syntax	Description
<code>Bytes send(     Message&amp; msg);</code>	Used when <code>queueName</code> has been previously set by the <a href="#">setQueueName()</a> method.
<code>Bytes send(     Message&amp; msg,     string&amp; queue);</code>	Enqueue the <code>Message</code> to the specified <code>queueName</code> .

Parameter	Description
<code>msg</code>	The <code>Message</code> that will be enqueued.
<code>queue</code>	The name of a valid queue in the database.

## setNull()

Frees memory associated with the `Producer`. Unless working in inner scope, this call should be made before terminating the `Connection`.

### Syntax

```
void setNull();
```

## setQueueName()

Specifies the name of a queue on which the `Messages` will be enqueued. Typically used when enqueueing multiple messages to the same queue.

### Syntax

```
void setQueueName(
    const string& queue);
```

Parameter	Description
queue	The name of a valid queue in the database, to which the <code>Messages</code> will be enqueued.

## setRelativeMessageId()

Specifies the `Message` id to be referenced in the sequence deviation operation. If the sequence deviation is not specified, this parameter will be ignored. Can be set for each enqueueing of a `Message`.

### Syntax

```
void setRelativeMessageId(
    const Bytes& msgid);
```

Parameter	Description
msgid	The id of the relative <code>Message</code> .

## setSequenceDeviation()

Specifies whether `Message` being enqueued should be dequeued before other `Message(s)` already in the queue. Can be set for each enqueueing of a `Message`.

### Syntax

```
void setSequenceDeviation(
    EnqueueSequence option);
```

Parameter	Description
option	The enqueue sequence being set, defined in <a href="#">Table 13-32</a> on page 13-167.

## setTransformation()

Specifies transformation function applied before enqueueing the Message.

### Syntax

```
void setTransformation(  
    string &fName);
```

Parameter	Description
fName	SQL transformation function.

## setVisibility()

Specifies transaction behavior of the enqueue request. Can be set for each enqueueing of a Message.

### Syntax

```
void setVisibility(  
    Visibility option);
```

Parameter	Description
option	Visibility option being set, defined in <a href="#">Table 13-32</a> on page 13-167.

## Ref Class

The mapping in the C++ programming language of an SQL REF value, which is a reference to an SQL structured type value in the database.

Each REF value has a unique identifier of the object it refers to. An SQL REF value may be used in place of the SQL structured type it references; it may be used as either a column value in a table or an attribute value in a structured type.

Because an SQL REF value is a logical pointer to an SQL structured type, a Ref object is by default also a logical pointer; thus, retrieving an SQL REF value as a Ref object does not materialize the attributes of the structured type on the client.

The only methods valid on a NULL Ref object are `isNull()`, and `operator=()`.

A Ref object can be saved to persistent storage and is de-referenced through `operator*()`, `operator->()` or `ptr()` methods. T must be a class derived from `PObject`. In the following sections, `T*` and `PObject*` are used interchangeably.

**Table 13–34 Enumerated Values Used by Ref Class**

Attribute	Options
LockOptions	<ul style="list-style-type: none"> <li>▪ <code>OCCI_LOCK_NONE</code> clears the lock setting on the Ref object.</li> <li>▪ <code>OCCI_LOCK_X</code> indicates that the object should be locked, and to wait for the lock to be available if the object is locked by another session.</li> <li>▪ <code>OCCI_LOCK_X_NOWAIT</code> indicates that the object should be locked, and returns an error if it is locked by another session.</li> </ul>
PrefetchOption	<ul style="list-style-type: none"> <li>▪ <code>OCCI_MAX_PREFETCH_DEPTH</code> indicates that the fetch should be done to maximum depth.</li> </ul>

**Table 13–35 Summary of Ref Methods**

Method	Summary
<code>Ref()</code> on page 13-173	Ref object constructor.
<code>clear()</code> on page 13-173	Clears the reference.
<code>getConnection()</code> on page 13-173	Returns the connection this ref was created from.
<code>isClear()</code> on page 13-173	Checks if the Ref is cleared.
<code>isNull()</code> on page 13-173	Checks if the Ref is NULL.
<code>markDelete()</code> on page 13-174	Marks the referred object as deleted.
<code>operator-&gt;()</code> on page 13-174	Dereferences the Ref and pins the object if necessary.
<code>operator*()</code> on page 13-174	Dereferences the Ref and pins or fetches the object if necessary.
<code>operator==()</code> on page 13-174	Checks if the Ref and the pointer refer to the same object.
<code>operator!=()</code> on page 13-175	Checks if the Ref and the pointer refer to different objects.
<code>operator=()</code> on page 13-175	Assignment operator.
<code>ptr()</code> on page 13-175	Returns a pointer to a <code>PObject</code> . Dereferences the Ref and pins or fetches the object if necessary.
<code>setLock()</code> on page 13-175	Sets the lock option for the object referred from this.
<code>setNull()</code> on page 13-176	Sets the Ref to NULL.

**Table 13–35 (Cont.) Summary of Ref Methods**

Method	Summary
<a href="#">setPrefetch()</a> on page 13-176	Sets the prefetch options for complex object retrieval.
<a href="#">unmarkDelete()</a> on page 13-176	Unmarks for delete the object referred by this.

## Ref()

Ref object constructor.

Syntax	Description
<code>Ref();</code>	Creates a NULL Ref .
<code>Ref(     const Ref&lt;T&gt; &amp;src);</code>	Creates a copy of Ref .

Parameter	Description
<code>src</code>	The Ref that is being copied.

## clear()

This method clears the Ref object.

### Syntax

```
void clear();
```

## getConnection()

Returns the connection from which the Ref object was instantiated.

### Syntax

```
const Connection *getConnection() const;
```

## isClear()

This method checks if Ref object is cleared.

### Syntax

```
bool isClear() const;
```

## isNull()

This method tests whether the Ref object is NULL. If the Ref object is NULL, then TRUE is returned; otherwise, FALSE is returned.

### Syntax

```
bool isNull() const;
```

## markDelete()

This method marks the referenced object as deleted.

### Syntax

```
void markDelete();
```

## operator->()

This method dereferences the `Ref` object and pins, or fetches the referenced object if necessary. This might result in prefetching a graph of objects if prefetch attributes of the referenced object are set.

Syntax	Description
<code>T *operator-&gt;();</code>	Dereferences and pins or fetches a non-const <code>Ref</code> object.
<code>const T *operator-&gt;() const;</code>	Dereferences and pins or fetches a <code>const Ref</code> object.

## operator\*()

This method dereferences the `Ref` object and pins or fetches the referenced object if necessary. This might result in prefetching a graph of objects if prefetch attributes of the referenced object are set. The object does not need to be deleted. Destructor would be automatically called when it goes out of scope.

Syntax	Description
<code>T&amp; operator*();</code>	Dereferences and pins or fetches a non-const <code>Ref</code> object.
<code>const T&amp; operator*() const;</code>	Dereferences and pins or fetches a <code>const Ref</code> object.

## operator==()

This method tests whether two `Ref` objects are referencing the same object. If the `Ref` objects are referencing the same object, then `TRUE` is returned; otherwise, `FALSE` is returned.

### Syntax

```
bool operator == (  
    const Ref<T> &ref) const;
```

Parameter	Description
<code>ref</code>	The <code>Ref</code> object of the object to be compared.

## operator!==( )

This method tests whether two `Ref` objects are referencing the same object. If the `Ref` objects are not referencing the same object, then `TRUE` is returned; otherwise, `FALSE` is returned.

### Syntax

```
bool operator!= (
    const Ref<T> &ref) const;
```

Parameter	Description
<code>ref</code>	The <code>Ref</code> object of the object to be compared.

## operator==( )

Assigns the `Ref` or the object to a `Ref`. For the first case, the `Refs` are assigned and for the second case, the `Ref` is constructed from the object and then assigned.

Syntax	Description
<code>Ref&lt;T&gt;&amp; operator=(     const Ref&lt;T&gt; &amp;src);</code>	Assigns a <code>Ref</code> to a <code>Ref</code> .
<code>Ref&lt;T&gt;&amp; operator=(     const T *)obj;</code>	Assigns a <code>Ref</code> to an object.

Parameter	Description
<code>src</code>	The source <code>Ref</code> object to be assigned.
<code>obj</code>	The source object pointer whose <code>Ref</code> object is to be assigned.

## ptr( )

Returns a pointer to a `PObject`. This operator dereferences the `Ref` and pins or fetches the object if necessary. This might result in prefetching a graph of objects if prefetch attributes of the `Ref` are set.

Syntax	Description
<code>T *ptr( );</code>	Returns a pointer of a non-const <code>Ref</code> object.
<code>const T *ptr( ) const;</code>	Returns a pointer of a const <code>Ref</code> object.

## setLock( )

This method specifies how the object should be locked when dereferenced.

### Syntax

```
void setLock(lockOptions);
```

Argument	Description
lockOptions	The lock options as defined by <code>LockOptions</code> in <a href="#">Table 13-34</a> on page 13-172.

## setNull()

This method sets the `Ref` object to `NULL`.

### Syntax

```
void setNull();
```

## setPrefetch()

Sets the prefetching options for complex object retrieval. This method specifies depth up to which all objects reachable from this object through `Refs` (transitive closure) should be prefetched. If only selected attribute types are to be prefetched, then the first version of the method should be used. This method specifies which `Ref` attributes of the object it refers to should be followed for prefetching of the objects (complex object retrieval) and how many levels deep those links should be followed.

Syntax	Description
<pre>void setPrefetch(     const string &amp;typeName,     unsigned int depth);</pre>	Sets the prefetching options for complex object retrieval, using type name and depth.
<pre>void setPrefetch(     unsigned int depth);</pre>	Sets the prefetching options for complex object retrieval, using depth only.
<pre>void setPrefetch(     const string &amp;schName,     const string &amp;typeName,     unsigned int depth);</pre>	Sets the prefetching options for complex object retrieval, using schema, type name, and depth.
<pre>void setPrefetch(     const UString &amp;schName,     const UString &amp;typeName,     unsigned int depth);</pre>	Sets the prefetching options for complex object retrieval, using schema, type name, and depth, and <code>UString</code> support.

Parameter	Description
typeName	Type of the <code>Ref</code> attribute to be prefetched.
schName	Schema name of the <code>Ref</code> attribute to be prefetched.
depth	Depth level to which the links should be followed; can use <code>PrefetchOption</code> as defined in <a href="#">Table 13-34</a> on page 13-172.

## unmarkDelete()

This method unmarks the referred object as dirty and available for deletion.

### Syntax

```
void unmarkDelete();
```



## RefAny Class

The `RefAny` class is designed to support a reference to any type. Its primary purpose is to handle generic references and allow conversions of `Ref` in the type hierarchy. A `RefAny` object can be used as an intermediary between any two types, `Ref<x>` and `Ref<y>`, where `x` and `y` are different types.

**Table 13–36 Summary of RefAny Methods**

Method	Summary
<a href="#">RefAny()</a> on page 13-177	Constructor for <code>RefAny</code> class.
<a href="#">clear()</a> on page 13-178	Clears the reference.
<a href="#">getConnection()</a> on page 13-178	Returns the connection this ref was created from.
<a href="#">isNull()</a> on page 13-178	Checks if the <code>RefAny</code> object is <code>NULL</code> .
<a href="#">markDelete()</a> on page 13-178	Marks the object as deleted.
<a href="#">operator=()</a> on page 13-178	Assignment operator for <code>RefAny</code> .
<a href="#">operator==(())</a> on page 13-178	Checks if this <code>RefAny</code> object is equal to a specified <code>RefAny</code> .
<a href="#">operator!=(())</a> on page 13-179	Checks if not equal.
<a href="#">unmarkDelete()</a> on page 13-179	Unmarks the object as deleted.

## RefAny()

A `Ref<T>` can always be converted to a `RefAny`; there is a method to perform the conversion in the `Ref<T>` template. Each `Ref<T>` has a constructor and assignment operator that takes a reference to `RefAny`.

Syntax	Description
<code>RefAny();</code>	Creates a <code>NULL</code> <code>RefAny</code> .
<code>RefAny(   const Connection *sessptr,   const OCIRef *ref);</code>	Creates a <code>RefAny</code> from a session pointer and a reference.
<code>RefAny(   const RefAny&amp; src);</code>	Creates a <code>RefAny</code> as a copy of another <code>RefAny</code> object.

Parameter	Description
<code>sessptr</code>	Session pointer
<code>ref</code>	A reference
<code>src</code>	The source <code>RefAny</code> object to be assigned

## clear()

This method clears the reference.

**Syntax**

```
void clear();
```

**getConnection()**

Returns the connection from which this reference was instantiated.

**Syntax**

```
const Connection* getConnection() const;
```

**isNull()**

Returns TRUE if the object pointed to by this ref is NULL else FALSE.

**Syntax**

```
bool isNull() const;
```

**markDelete()**

This method marks the referred object as deleted.

**Syntax**

```
void markDelete();
```

**operator=()**

Assignment operator for RefAny.

**Syntax**

```
RefAny& operator=(  
    const RefAny& src);
```

Parameter	Description
src	The source RefAny object to be assigned.

**operator==(())**

Compares this ref with a RefAny object and returns TRUE if both the refs are referring to the same object in the cache, otherwise it returns FALSE.

**Syntax**

```
bool operator==(   
    const RefAny &refAnyR) const;
```

Parameter	Description
refAnyR	RefAny object to which the comparison is made.

## operator!==( )

Compares this ref with the RefAny object and returns TRUE if both the refs are not referring to the same object in the cache, otherwise it returns FALSE.

### Syntax

```
bool operator!= (
    const RefAny &refAnyR) const;
```

Parameter	Description
refAnyR	RefAny object to which the comparison is made.

## unmarkDelete()

This method unmarks the referred object as dirty.

### Syntax

```
void unmarkDelete();
```

## ResultSet Class

A `ResultSet` provides access to a table of data generated by executing a `Statement`. Table rows are retrieved in sequence. Within a row, column values can be accessed in any order.

A `ResultSet` maintains a cursor pointing to its current row of data. Initially the cursor is positioned before the first row. The `next` method moves the cursor to the next row.

The `getxxx()` methods retrieve column values for the current row. You can retrieve values using the index number of the column. Columns are numbered beginning at 1. For the `getxxx()` methods, OCCI attempts to convert the underlying data to the specified C++ type and returns a C++ value. SQL types are mapped to C++ types with the `ResultSet::getxxx()` methods.

The number, types and properties of a `ResultSet`'s columns are provided by the `MetaData` object returned by the `getColumnListMetaData()` method.

**Table 13–37 Enumerated Values Used by ResultSet Class**

Attribute	Options
Status	<ul style="list-style-type: none"> <li>▪ <code>DATA_AVAILABLE</code> indicates that data for one or more rows was successfully fetched from the server; up to the requested number of rows (<code>numRows</code>) were returned. When in streamed mode, use the <code>getNumArrayRows()</code> method to determine the exact number of rows retrieved when <code>numRows</code> is greater than 1.</li> <li>▪ <code>STREAM_DATA_AVAILABLE</code> indicates that the application should call the <code>getCurrentStreamColumn()</code> method and read stream.</li> <li>▪ <code>END_OF_FETCH</code> indicates that no data was available for fetching.</li> </ul>

**Table 13–38 Summary of ResultSet Methods**

Method	Description
<code>cancel()</code> on page 13-182	Cancels the <code>ResultSet</code> .
<code>closeStream()</code> on page 13-182	Closes the specified <code>Stream</code> .
<code>getBDouble()</code> on page 13-183	Returns the value of a column in the current row as a <code>BDouble</code> .
<code>getBfile()</code> on page 13-183	Returns the value of a column in the current row as a <code>Bfile</code> .
<code>getBFloat()</code> on page 13-183	Returns the value of a column in the current row as a <code>BFloat</code> .
<code>getBlob()</code> on page 13-183	Returns the value of a column in the current row as a <code>Blob</code> object.
<code>getBytes()</code> on page 13-184	Returns the value of a column in the current row as a <code>Bytes</code> array.
<code>getCharSet()</code> on page 13-184	Returns the character set in which data would be fetched.
<code>getCharSetUString()</code> on page 13-184	Returns the character set in which data would be fetched as a <code>UString</code> .
<code>getClob()</code> on page 13-184	Returns the value of a column in the current row as a <code>Clob</code> object.

**Table 13–38 (Cont.) Summary of ResultSet Methods**

Method	Description
<a href="#">getColumnListMetaData()</a> on page 13-185	Returns the describe information of the result set columns as a <code>MetaData</code> object.
<a href="#">getCurrentStreamColumn()</a> on page 13-185	Returns the column index of the current readable <code>Stream</code> .
<a href="#">getCurrentStreamRow()</a> on page 13-185	Returns the current row of the <code>ResultSet</code> being processed.
<a href="#">getCursor()</a> on page 13-185	Returns the nested cursor as a <code>ResultSet</code> .
<a href="#">getDate()</a> on page 13-186	Returns the value of a column in the current row as a <code>Date</code> object.
<a href="#">getDatabaseNCHARParam()</a> on page 13-186	Returns whether data is in NCHAR character set or not.
<a href="#">getDouble()</a> on page 13-186	Returns the value of a column in the current row as a C++ double.
<a href="#">getFloat()</a> on page 13-187	Returns the value of a column in the current row as a C++ float.
<a href="#">getInt()</a> on page 13-187	Returns the value of a column in the current row as a C++ int.
<a href="#">getIntervalDS()</a> on page 13-187	Returns the value of a column in the current row as a <code>IntervalDS</code> .
<a href="#">getIntervalYM()</a> on page 13-187	Returns the value of a column in the current row as a <code>IntervalYM</code> .
<a href="#">getMaxColumnSize()</a> on page 13-188	Returns the maximum amount of data to read from a column.
<a href="#">getNumArrayRows()</a> on page 13-188	Returns the actual number of rows fetched in the last array fetch.
<a href="#">getNumber()</a> on page 13-188	Returns the value of a column in the current row as a <code>Number</code> object.
<a href="#">getObject()</a> on page 13-188	Returns the value of a column in the current row as a <code>PObject</code> .
<a href="#">getRef()</a> on page 13-189	Returns the value of a column in the current row as a <code>Ref</code> .
<a href="#">getRowid()</a> on page 13-189	Returns the current ROWID for a <code>SELECT FOR UPDATE</code> statement.
<a href="#">getRowPosition()</a> on page 13-189	Returns the row id of the current row position.
<a href="#">getStatement()</a> on page 13-189	Returns the <code>Statement</code> of the <code>ResultSet</code> .
<a href="#">getStream()</a> on page 13-189	Returns the value of a column in the current row as a <code>Stream</code> .
<a href="#">getString()</a> on page 13-190	Returns the value of a column in the current row as a string.
<a href="#">getTimestamp()</a> on page 13-190	Returns the value of a column in the current row as a <code>Timestamp</code> object.
<a href="#">getUInt()</a> on page 13-190	Returns the value of a column in the current row as a C++ unsigned int
<a href="#">getUString()</a> on page 13-190	Returns the value of a column in the current row as a <code>UString</code> .
<a href="#">getVector()</a> on page 13-191	Returns the specified collection parameter as a vector.

**Table 13–38 (Cont.) Summary of ResultSet Methods**

Method	Description
<a href="#">getVectorOfRefs()</a> on page 13-193	Returns the column in the current position as a vector of <code>Refs</code> .
<a href="#">isNull()</a> on page 13-193	Checks whether the value is <code>NULL</code> .
<a href="#">isTruncated()</a> on page 13-193	Checks whether truncation has occurred.
<a href="#">next()</a> on page 13-194	Makes the next row the current row in a <code>ResultSet</code> .
<a href="#">preTruncationLength()</a> on page 13-194	Returns the actual length of the parameter before truncation.
<a href="#">setBinaryStreamMode()</a> on page 13-194	Specifies that a column is to be returned as a binary stream.
<a href="#">setCharacterStreamMode()</a> on page 13-195	Specifies that a column is to be returned as a character stream.
<a href="#">setCharSet()</a> on page 13-195	Specifies the character set in which the data is to be returned.
<a href="#">setCharSetUString()</a> on page 13-195	Specifies the character set in which the data is to be returned.
<a href="#">setDatabaseNCHARParam()</a> on page 13-196	If the parameter is going to be retrieved from a column that contains data in the database's <code>NCHAR</code> character set, then <code>OCCI</code> must be informed by passing a true value.
<a href="#">setDataBuffer()</a> on page 13-196	Specifies the data buffer into which data is to be fetched, or the gather and scatter binds and defines made.
<a href="#">setErrorOnNull()</a> on page 13-197	Enables Or Disables exception when <code>NULL</code> value is read.
<a href="#">setErrorOnTruncate()</a> on page 13-197	Enables Or Disables exception when truncation occurs.
<a href="#">setMaxColumnSize()</a> on page 13-197	Specifies the maximum amount of data to read from a column.
<a href="#">status()</a> on page 13-198	Returns the current status of the <code>ResultSet</code> .

## cancel()

This method cancels the result set.

### Syntax

```
void cancel();
```

## closeStream()

This method closes the stream specified by the parameter `stream`.

### Syntax

```
void closeStream(
    Stream *stream);
```

Parameter	Description
stream	The Stream to be closed.

## getBDouble()

This method returns the value of a column in the current row as a `BDouble`. If the value is `SQL NULL`, the result is `NULL`.

### Syntax

```
BDouble getBDouble(
    unsigned int colIndex);
```

Parameter	Description
colIndex	Column index, first column is 1, second is 2, and so on.

## getBfile()

This method returns the value of a column in the current row as a `Bfile`. Returns the column value; if the value is `SQL NULL`, the result is `NULL`.

### Syntax

```
Bfile getBfile(
    unsigned int colIndex);
```

Parameter	Description
colIndex	Column index, first column is 1, second is 2, and so on.

## getBFloat()

This method returns the value of a column in the current row as a `BFloat`. If the value is `SQL NULL`, the result is `NULL`.

### Syntax

```
BFloat getBFloat(
    unsigned int colIndex);
```

Parameter	Description
colIndex	Column index, first column is 1, second is 2, and so on.

## getBlob()

Get the value of a column in the current row as an `Blob`. Returns the column value; if the value is `SQL NULL`, the result is `NULL`.

**Syntax**

```
Blob getBlob(
    unsigned int colIndex);
```

Parameter	Description
colIndex	Column index, first column is 1, second is 2, and so on.

**getBytes()**

Get the value of a column in the current row as a `Bytes` array. The bytes represent the raw values returned by the server. Returns the column value; if the value is `SQL NULL`, the result is `NULL` array

**Syntax**

```
Bytes getBytes(
    unsigned int colIndex);
```

Parameter	Description
colIndex	Column index, first column is 1, second is 2, and so on.

**getCharSet()**

Gets the character set in which data would be fetched, as a string.

**Syntax**

```
string getCharSet(
    unsigned int colIndex) const;
```

Parameter	Description
colIndex	Column index, first column is 1, second is 2, and so on.

**getCharSetUString()**

Gets the character set in which data would be fetched, as a string.

**Syntax**

```
UString getCharSetUString(
    unsigned int colIndex) const;
```

Parameter	Description
colIndex	Column index, first column is 1, second is 2, and so on.

**getClob()**

Get the value of a column in the current row as a `Clob`. Returns the column value; if the value is `SQL NULL`, the result is `NULL`.



**Syntax**

```
Clob getClob(
    unsigned int colIndex);
```

Parameter	Description
colIndex	Column index, first column is 1, second is 2, and so on.

**getColumnListMetaData()**

The number, types and properties of a `ResultSet`'s columns are provided by the `getMetaData` method. Returns the description of a `ResultSet`'s columns. This method will return the value of the given column as a `PObject`. The type of the C++ object will be the C++ `PObject` type corresponding to the column's SQL type registered with `Environment`'s map. This method is used to materialize data of SQL user-defined types.

**Syntax**

```
vector<MetaData> getColumnListMetaData() const;
```

**getCurrentStreamColumn()**

If the result set has any input `Stream` parameters, this method returns the column index of the current input `Stream` that must be read. If no output `Stream` needs to be read, or there are no input `Stream` columns in the result set, this method returns 0. Returns the column index of the current input `Stream` column that must be read.

**Syntax**

```
unsigned int getCurrentStreamColumn() const;
```

**getCurrentStreamRow()**

If the result has any input `Streams`, this method returns the current row of the result set that is being processed by `OCCI`. If this method is called after all the rows in the set of array of rows have been processed, it returns 0. Returns the row number of the current row that is being processed. The first row is numbered 1 and so on.

**Syntax**

```
unsigned int getCurrentStreamRow() const;
```

**getCursor()**

Get the nested cursor as an `ResultSet`. Data can be fetched from this result set. A nested cursor results from a nested query with a `CURSOR(SELECT ... )` clause:

```
SELECT ename,
       CURSOR(SELECT dname, loc FROM dept)
FROM emp WHERE ename = 'JONES'
```

Note that if there are multiple REF CURSORS being returned, data from each cursor must be completely fetched before retrieving the next REF CURSOR and starting fetch on it. Returns A ResultSet for the nested cursor.

**Syntax**

```
ResultSet * getCursor(  
    unsigned int colIndex);
```

Parameter	Description
colIndex	Column index, first column is 1, second is 2, and so on.

**getDatabaseNCHARParam()**

Returns whether data is in NCHAR character set or not.

**Syntax**

```
bool getDatabaseNCHARParam(  
    unsigned int paramIndex) const;
```

Parameter	Description
paramIndex	Parameter index, first parameter is 1, second is 2, and so on.

**getDate()**

Get the value of a column in the current row as a Date object. Returns the column value; if the value is SQL NULL, the result is NULL.

**Syntax**

```
Date getDate(  
    unsigned int colIndex);
```

Parameter	Description
colIndex	Column index, first column is 1, second is 2, and so on.

**getDouble()**

Gets the value of a column in the current row as a C++ double. Returns the column value; if the value is SQL NULL, the result is 0.

**Syntax**

```
double getDouble(  
    unsigned int colIndex);
```

Parameter	Description
colIndex	Column index, first column is 1, second is 2, and so on.

## getFloat()

Get the value of a column in the current row as a C++ float. Returns the column value; if the value is SQL NULL, the result is 0.

### Syntax

```
float getFloat(
    unsigned int colIndex);
```

Parameter	Description
colIndex	Column index, first column is 1, second is 2, and so on.

## getInt()

Get the value of a column in the current row as a C++ int. Returns the column value; if the value is SQL NULL, the result is 0.

### Syntax

```
int getInt(
    unsigned int colIndex);
```

Parameter	Description
colIndex	Column index, first column is 1, second is 2, and so on.

## getIntervalDS()

Get the value of a column in the current row as a IntervalDS object. Returns the column value; if the value is SQL NULL, the result is NULL.

### Syntax

```
IntervalDS getIntervalDS(
    unsigned int colIndex);
```

Parameter	Description
colIndex	Column index, first column is 1, second is 2, and so on.

## getIntervalYM()

Get the value of a column in the current row as a IntervalYM object. Returns the column value; if the value is SQL NULL, the result is NULL.

### Syntax

```
IntervalYM getIntervalYM(
    unsigned int colIndex);
```

Parameter	Description
colIndex	Column index, first column is 1, second is 2, and so on.

## getMaxColumnSize()

Get the maximum amount of data to read for a column.

### Syntax

```
unsigned int getMaxColumnSize(  
    unsigned int colIndex) const;
```

Parameter	Description
colIndex	Column index, first column is 1, second is 2, and so on.

## getNumArrayRows()

Returns the actual number of rows fetched in the last array fetch. Used in conjunction with the [next\(\)](#) method. This method cannot be used for non-array fetches.

### Syntax

```
unsigned int getNumArrayRows() const;
```

## getNumber()

Get the value of a column in the current row as a `Number` object. Returns the column value; if the value is SQL NULL, the result is NULL.

### Syntax

```
Number getNumber(  
    unsigned int colIndex);
```

Parameter	Description
colIndex	Column index, first column is 1, second is 2, and so on.

## getObject()

Returns a pointer to a `PObject` holding the column value.

### Syntax

```
PObject * getObject(  
    unsigned int colIndex);
```

Parameter	Description
colIndex	Column index; first column is 1, second is 2, and so on.

## getRef()

Get the value of a column in the current row as a `RefAny`. Retrieving a `Ref` value does not materialize the data to which `Ref` refers. Also the `Ref` value remains valid while the session or connection on which it is created is open. Returns a `RefAny` holding the column value.

### Syntax

```
RefAny getRef(
    unsigned int colIndex);
```

Parameter	Description
<code>colIndex</code>	Column index, first column is 1, second is 2, and so on.

## getRowid()

Get the current row id for a `SELECT ... FOR UPDATE` statement. The row id can be bound to a prepared `DELETE` statement and so on. Returns current `rowid` for a `SELECT ... FOR UPDATE` statement.

### Syntax

```
Bytes getRowid(
    unsigned int colIndex);
```

Parameter	Description
<code>colIndex</code>	Column index, first column is 1, second is 2, and so on.

## getRowPosition()

Get the `rowid` of the current row position.

### Syntax

```
Bytes getRowPosition() const;
```

## getStatement()

This method returns the statement of the `ResultSet`.

### Syntax

```
Statement* getStatement() const;
```

## getStream()

This method returns the value of a column in the current row as a `Stream`.

### Syntax

```
Stream * getStream(
```

## getString()

---

```
unsigned int colIndex);
```

Parameter	Description
colIndex	Column index, first column is 1, second is 2, and so on.

## getString()

Get the value of a column in the current row as a string. Returns the column value; if the value is SQL NULL, the result is an empty string.

### Syntax

```
string getString(  
    unsigned int colIndex);
```

Parameter	Description
colIndex	Column index, first column is 1, second is 2, and so on.

## getTimestamp()

Get the value of a column in the current row as a Timestamp object. Returns the column value; if the value is SQL NULL, the result is NULL.

### Syntax

```
Timestamp getTimestamp(  
    unsigned int colIndex);
```

Parameter	Description
colIndex	Column index, first column is 1, second is 2, and so on.

## getUInt()

Get the value of a column in the current row as a C++ int. Returns the column value; if the value is SQL NULL, the result is 0.

### Syntax

```
unsigned int getUInt(  
    unsigned int colIndex);
```

Parameter	Description
colIndex	Column index, first column is 1, second is 2, and so on.

## getUString()

Returns the value as a UString.

---



---

**Note:** This method should be called only if the environment's character set is UTF16, or if `setCharset()` method has been called to explicitly retrieve UTF16 data.

---



---

### Syntax

```
UString getUString(
    unsigned int colIndex);
```

Parameter	Description
colIndex	Column index; first column is 1, second is 2, and so on.

## getVector()

This method returns the column in the current position as a vector. The column should be a collection type (varray or nested table). The SQL type of the elements in the collection should be compatible with the data type of the objects in the vector.

Syntax	Description
<pre>void getVector(     ResultSet *rs,     unsigned int colIndex,     vector&lt;BDouble&gt; &amp;vect);</pre>	Used for BDouble vectors.
<pre>void getVector(     ResultSet *rs,     unsigned int colIndex,     vector&lt;Bfile&gt; &amp;vect);</pre>	Used for Bfile vectors.
<pre>void getVector(     ResultSet *rs,     unsigned int colIndex,     vector&lt;BFloat&gt; &amp;vect);</pre>	Used for BFloat vectors.
<pre>void getVector(     ResultSet *rs,     unsigned int colIndex,     vector&lt;Blob&gt; &amp;vect);</pre>	Used for Blob vectors.
<pre>void getVector(     ResultSet *rs,     unsigned int colIndex,     vector&lt;Clob&gt; &amp;vect);</pre>	Used for Clob vectors.
<pre>void getVector(     ResultSet *rs,     unsigned int colIndex,     vector&lt;Date&gt; &amp;vect);</pre>	Used for vectors of <a href="#">Date Class</a> .
<pre>void getVector(     ResultSet *rs,     unsigned int colIndex,     vector&lt;double&gt; &amp;vect);</pre>	Used for vectors of double type.
<pre>void getVector(     ResultSet *rs,     unsigned int colIndex,     vector&lt;float&gt; &amp;vect);</pre>	Used for vectors of float type.

Syntax	Description
<pre>void getVector(     ResultSet *rs,     unsigned int colIndex,     vector&lt;int&gt; &amp;vect);</pre>	Used for vectors of int type.
<pre>void getVector(     ResultSet *rs,     unsigned int colIndex,     vector&lt;IntervalDS&gt; &amp;vect);</pre>	Used for vectors of <a href="#">IntervalDS Class</a> .
<pre>void getVector(     ResultSet *rs,     unsigned int colIndex,     vector&lt;IntervalYM&gt; &amp;vect);</pre>	Used for vectors of <a href="#">IntervalYM Class</a> .
<pre>void getVector(     ResultSet *rs,     unsigned int colIndex,     vector&lt;Number&gt; &amp;vect);</pre>	Used for vectors of <a href="#">Number Class</a> .
<pre>void getVector(     ResultSet *rs,     unsigned int colIndex,     vector&lt;Ref&lt;T&gt;&gt; &amp;vect);</pre>	Available only on platforms where partial ordering of function templates is supported. This function may be deprecated in the future. <a href="#">getVectorOfRefs()</a> can be used instead.
<pre>void getVector(     ResultSet *rs,     unsigned int colIndex,     vector&lt;RefAny&gt; &amp;vect);</pre>	Used for vectors of <a href="#">RefAny Class</a> .
<pre>void getVector(     ResultSet *rs,     unsigned int colIndex,     vector&lt;string&gt; &amp;vect);</pre>	Used for vectors of string type.
<pre>void getVector(     ResultSet *rs,     unsigned int colIndex,     vector&lt;T *&gt; &amp;vect);</pre>	Intended for use on platforms where partial ordering of function templates is supported.
<pre>void getVector(     ResultSet *rs,     unsigned int colIndex,     vector&lt;T&gt; &amp;vect);</pre>	Intended for use on platforms where partial ordering of function templates is not supported, such as Windows NT and z/OS.
<pre>void getVector(     ResultSet *rs,     unsigned int colIndex,     vector&lt;Timestamp&gt; &amp;vect);</pre>	Used for vectors of <a href="#">Timestamp Class</a> .
<pre>void getVector(     ResultSet *rs,     unsigned int colIndex,     vector&lt;unsigned int&gt; &amp;vect);</pre>	Used for vectors of unsigned int type.
<pre>void getVector(     ResultSet *rs,     unsigned int colIndex,     vector&lt;UString&gt; &amp;vect);</pre>	Used for vectors of <a href="#">UString Class</a> ; globalization enabled.



Parameter	Description
rs	The result set
colIndex	Column index, first column is 1, second is 2, and so on.
vect	The reference to the vector (OUT parameter).

## getVectorOfRefs()

Returns the column in the current position as a vector of REFS. The column should be a collection type (varray or nested table) of REFS. It is recommend to use this function instead of specialized method [getVector\(\)](#) for `Ref<T>`.

### Syntax

```
void getVectorOfRefs(
    ResultSet *rs,
    unsigned int colIndex,
    vector< Ref<T> > &vect);
```

Parameter	Description
rs	The result set
colIndex	Column index, first column is 1, second is 2, and so on.
vect	The reference to the vector of REFS (OUT parameter).

## isNull()

A column may have the value of SQL NULL; `isNull()` reports whether the last column read had this special value. Note that you must first call `getxxx()` on a column to try to read its value and then call `isNull()` to find if the value was the SQL NULL. Returns TRUE if last column read was SQL NULL.

### Syntax

```
bool isNull(
    unsigned int colIndex) const;
```

Parameter	Description
colIndex	Column index, first column is 1, second is 2, and so on.

## isTruncated()

This method checks whether the value of the parameter is truncated. If the value of the parameter is truncated, then TRUE is returned; otherwise, FALSE is returned.

### Syntax

```
bool isTruncated(
    unsigned int paramIndex) const;
```

Parameter	Description
paramIndex	Parameter index, first parameter is 1, second is 2, and so on.

## next()

This method fetches a specified number of rows, `numRows`, from a previously executed query, and reports the `Status` of this fetch as defined in [Table 13-37](#).

For non-streamed mode, `next()` will only return the status of `DATA_AVAILABLE` or `END_OF_FETCH`.

- When fetching one row at a time (`numRows=1`), process the data using `getxxx()` methods.
- When fetching several rows at once (`numRows>1`), as in an Array Fetch, you must use the `setDataBuffer()` method to specify the location of your preallocated buffers before invoking `next()`.

Up to `numRows` data records would populate the buffers specified by the `setDataBuffer()` call. To determine exactly how many records were returned, use the `getNumArrayRows()` method.

### Syntax

```
Status next(
    unsigned int numRows = 1);
```

Parameter	Description
numRows	Number of rows to fetch for array fetches.

## preTruncationLength()

Returns the actual length of the parameter before truncation.

### Syntax

```
int preTruncationLength(
    unsigned int paramIndex) const;
```

Parameter	Description
paramIndex	Parameter index, first parameter is 1, second is 2, and so on.

## setBinaryStreamMode()

Defines that a column is to be returned as a binary stream by the `getStream` method.

### Syntax

```
void setBinaryStreamMode(
    unsigned int colIndex,
    unsigned int size);
```

Parameter	Description
colIndex	Column index, first column is 1, second is 2, and so on.
size	The amount of data to be read as a binary stream.

## setCharacterStreamMode()

Defines that a column is to be returned as a character stream by the [getStream\(\)](#) method.

### Syntax

```
void setCharacterStreamMode(
    unsigned int colIndex,
    unsigned int size);
```

Parameter	Description
colIndex	Column index, first column is 1, second is 2, and so on.
size	The amount of data to be read as a character stream.

## setCharSet()

Overrides the default character set for the specified column. Data is converted from the database character set to the specified character set for this column.

### Syntax

```
void setCharSet(
    unsigned int colIndex,
    string charSet);
```

Parameter	Description
colIndex	Column index, first column is 1, second is 2, and so on.
charSet	Desired character set, as a string.

## setCharSetUString()

Specifies the character set value as a `UString` in which the data is returned.

### Syntax

```
UString setCharSetUString(
    unsigned int colIndex,
    const UString &charSet);
```

Parameter	Description
colIndex	Column index, first column is 1, second is 2, and so on.
charSet	Desired character set, as a string.

## setDatabaseNCHARParam()

If the parameter is going to be retrieved from a column that contains data in the database's NCHAR character set, then OCI must be informed by passing a TRUE value. A FALSE can be passed to restore the default.

### Syntax

```
void setDatabaseNCHARParam(
    unsigned int paramIndex,
    bool isNCHAR);
```

Parameter	Description
paramIndex	Parameter index, first parameter is 1, second is 2, and so on.
isNCHAR	TRUE or FALSE.

## setDataBuffer()

Specifies a data buffer where data would be fetched or bound. The *buffer* parameter is a pointer to a user allocated data buffer. The current length of data must be specified in the *length* parameter. The amount of data should not exceed the *size* parameter. Finally, *type* is the data type of the data. Only non OCI and non C++ specific types can be used, such as STL string. OCI classes like *Bytes* and *Date* cannot be used.

If [setDataBuffer\(\)](#) is used to fetch data for array fetches, it should be called only once for each result set. Data for each row is assumed to be at `buffer (i- 1)` location, where *i* is the row number. Similarly, the length of the data would be assumed to be at `(length+ (i-1))`.

### Syntax

```
void setDataBuffer(
    unsigned int colIndex,
    void *buffer,
    Type type,
    sb4 size = 0,
    ub2 *length = NULL,
    sb2 *ind = NULL,
    ub2 *rc = NULL);
```

Parameter	Description
colIndex	Column index, first column is 1, second is 2, and so on.
buffer	Pointer to user-allocated buffer. For array fetches, it should have <code>numRows * size</code> bytes in it. For gather or scatter binds and defines, this structure stores the address of <code>OCIIOVec</code> and the number of <code>OCIIOVec</code> elements that start at that address.
type	Type of the data that is provided (or retrieved) in the buffer.
size	Size of the data buffer. For array fetches, it is the size of each element of the data items.
length	Pointer to the length of data in the buffer; for array fetches, it should be an array of length data for each buffer element; the size of the array should be equal to <code>arrayLength</code> .

Parameter	Description
ind	Pointer to an indicator variable or array (IN/OUT).
rc	Pointer to array of column level return codes (OUT).

## setErrorOnNull()

This method enables/disables exceptions for reading of NULL values on `colIndex` column of the result set.

### Syntax

```
void setErrorOnNull(
    unsigned int colIndex,
    bool causeException);
```

Parameter	Description
colIndex	Column index, first column is 1, second is 2, and so on.
causeException	Enable exceptions if TRUE. Disable if FALSE.

## setErrorOnTruncate()

This method enables/disables exceptions when truncation occurs.

### Syntax

```
void setErrorOnTruncate(
    unsigned int paramIndex,
    bool causeException);
```

Parameter	Description
paramIndex	Parameter index, first parameter is 1, second is 2, and so on.
causeException	Enable exceptions if TRUE. Disable if FALSE.

## setMaxColumnSize()

Sets the maximum amount of data to read for a column.

### Syntax

```
void setMaxColumnSize(
    unsigned int colIndex,
    unsigned int max);
```

Parameter	Description
colIndex	Column index, first column is 1, second is 2, and so on.
max	The maximum amount of data to be read.

## status()

Returns the current `Status` of the result set, as defined in [Table 13–37](#). This method can be called repeatedly.

### Syntax

```
Status status() const;
```

## SQLException Class

The `SQLException` class provides information on generated errors, their codes and associated messages.

**Table 13–39 Summary of SQLException**

Method	Description
<a href="#">SQLException()</a> on page 13-199	SQLException constructor.
<a href="#">getErrorCode()</a> on page 13-199	Returns the database error code.
<a href="#">getMessage()</a> on page 13-200	Returns the error message <code>string</code> for this exception.
<a href="#">getNLSMessage()</a> on page 13-200	Returns the error message <code>string</code> for this exception (Unicode support).
<a href="#">getNLSUStringMessage()</a> on page 13-200	Returns the error message <code>UString</code> for this exception (Unicode support).
<a href="#">getUStringMessage()</a> on page 13-200	Returns the error message <code>UString</code> for this exception.
<a href="#">getXAErrorCode()</a> on page 13-200	Returns the error message <code>string</code> for this exception.
<a href="#">setErrorCtx()</a> on page 13-201	Sets the error context.
<a href="#">what()</a> on page 13-201	Returns the error message associated with the <code>SQLException</code> .

### SQLException()

This is the `SQLException` constructor.

Syntax	Description
<code>SQLException();</code>	Constructs a <code>NULL</code> <code>SQLException</code> object.
<code>SQLException(     const SQLException &amp;e);</code>	Constructs an <code>SQLException</code> object as a copy of another <code>SQLException</code> object.

Parameter	Description
<code>e</code>	The <code>SQLException</code> to be copied.

### getErrorCode()

Gets the database error code.

#### Syntax

```
int getErrorCode() const;
```

## getMessage()

Returns the error message string of this `SQLException` if it was created with an error message string. Returns `NULL` if the `SQLException` was created with no error message.

### Syntax

```
string getMessage() const;
```

## getNLSMessage()

Returns the error message string of this `SQLException` if it was created with an error message string. Passes the globalization enabled environment. Returns a `NULL` string if the `SQLException` was created with no error message. The error message will be in the character set associated with the environment.

### Syntax

```
string getNLSMessage(  
    Environment *env) const;
```

Parameter	Description
env	The globalization enabled environment.

## getNLSUStringMessage()

Returns the error message `UString` of this `SQLException` if it was created with an error message `UString`. Passes the globalization enabled environment. Returns a `NULL` `UString` if the `SQLException` was created with no error message. The error message will be in the character set associated with the environment.

### Syntax

```
UString getNLSUStringMessage(  
    Environment *env) const;
```

Parameter	Description
env	The globalization enabled environment.

## getUStringMessage()

Returns the error message `UString` of this `SQLException` if it was created with an error message `UString`. Returns a `NULL` `UString` if the `SQLException` was created with no error message. The error message will be in the character set associated with the environment.

### Syntax

```
UString getUStringMessage() const;
```



## getXAErrorCode()

Determine if the thrown exception is due to an XA or an SQL error.

Used by C++ XA applications with dynamic registration. Returns an XA error code if the exception is due to XA, or `XA_OK` otherwise.

### Syntax

```
int getXAErrorCode(
    const string &dbname) const;
```

Parameter	Description
dbname	The database name; same as the optional dbname provided in the Open String and used when connecting to the Resource Manager.

## setErrorCtx()

Sets the pointer to the error context.

### Syntax

```
void setErrorCtx(
    void *ctx);
```

Parameter	Description
ctx	The pointer to the error context.

## what()

Standard C++ compliant function; returns the error message associated with the `SQLException`.

### Syntax

```
const char *what() const throw();
```

## StatelessConnectionPool Class

This class represents a pool of stateless, authenticated connections to the database.

**Table 13–40 Enumerated Values Used by StatelessConnectionPool Class**

Attribute	Options
PoolType	<ul style="list-style-type: none"> <li>■ HETEROGENEOUS is the default state; connections with different authentication contexts can be created in the same pool.</li> <li>■ HOMOGENEOUS indicates that all connections in the pool will be authenticated with the username and password provided during pool creation. No proxy connections can be created. <code>minConn</code> and <code>incrConn</code> values are considered only in these HOMOGENEOUS pools.</li> <li>■ NO_RLB turns off runtime load balancing in the connection pool. Can be used with both HETEROGENEOUS and HOMOGENEOUS pools.</li> </ul>
BusyOption	<ul style="list-style-type: none"> <li>■ WAIT indicates that the thread waits and blocks until the connection becomes free.</li> <li>■ NOWAIT throws an error.</li> <li>■ FORCEGET indicates that a new connection will be created, even when maximum number of connections is opened and all are busy.</li> </ul>
DestroyMode	<ul style="list-style-type: none"> <li>■ DEFAULT indicates that if there are still active busy connections in the pool, ORA24422 error is thrown</li> <li>■ SPD_FORCE indicates that this means that any busy connections in the pool will be forcefully terminated and the pool destroyed (the user will lose memory corresponding to the number of connections forcefully terminated)</li> </ul>

**Table 13–41 Summary of StatelessConnectionPool Methods**

Method	Description
<a href="#">getAnyTaggedConnection()</a> on page 13-203	Returns a pointer to the connection object, without the restriction of a matching tag.
<a href="#">getAnyTaggedProxyConnection()</a> on page 13-204	Returns a proxy connection from a connection pool.
<a href="#">getBusyConnections()</a> on page 13-205	Returns the number of busy connections in the connection pool.
<a href="#">getBusyOption()</a> on page 13-205	Returns the behavior of the stateless connection pool when all the connections in the pool are busy and the number of connections have reached maximum
<a href="#">getConnection()</a> on page 13-205	Returns a pointer to the <code>Connection</code> object.
<a href="#">getIncrConnections()</a> on page 13-206	Returns the number of incremental connections in the connection pool.
<a href="#">getMaxConnections()</a> on page 13-207	Returns the maximum number of connections in the connection pool.
<a href="#">getMinConnections()</a> on page 13-207	Returns the minimum number of connections in the connection pool.
<a href="#">getOpenConnections()</a> on page 13-207	Returns the number of open connections in the connection pool.
<a href="#">getPoolName()</a> on page 13-207	Returns the name of the connection pool.

**Table 13–41 (Cont.) Summary of StatelessConnectionPool Methods**

Method	Description
<a href="#">getProxyConnection()</a> on page 13-207	Returns a proxy connection from a connection pool.
<a href="#">getTimeout()</a> on page 13-209	Returns the timeout period of a connection in the connection pool.
<a href="#">releaseConnection()</a> on page 13-209	Releases the connection back to the pool with an optional tag.
<a href="#">setBusyOption()</a> on page 13-209	Specifies the behavior of the stateless connection pool when: <ul style="list-style-type: none"> <li>■ all the connections in the pool are busy, and</li> <li>■ the number of connections have reached maximum.</li> </ul>
<a href="#">setPoolSize()</a> on page 13-210	Sets the maximum, minimum, and incremental number of pooled connections for the connection pool.
<a href="#">setTimeout()</a> on page 13-210	Sets the timeout period of a connection in the connection pool.
<a href="#">terminateConnection()</a> on page 13-211	Closes the connection and remove it from the pool.

## getAnyTaggedConnection()

Returns a pointer to the connection object, without the restriction of a matching tag.

This method works in an environment with enabled database resident connection pooling.

During the execution of this call, the pool is first searched based on the tag provided. If a connection with the specified tag exists, it is returned to the user. If a matching connection is not available, an appropriately authenticated untagged connection (with a NULL tag) is returned. In cases where an undated connection is not free, an appropriately authenticated connection with a different tag is returned.

A `getTag()` call to the `Connection` verifies that the connection tag is received.

Syntax	Description
<code>Connection *getAnyTaggedConnection( string &amp;tag="")=0;</code>	Returns a pointer to the connection object from a homogeneous stateless connection pool, without the restriction of a matching tag; <code>string</code> support.
<code>Connection* getAnyTaggedConnection( const UString &amp;tag)=0;</code>	Returns a pointer to the connection object from a homogeneous stateless connection pool, without the restriction of a matching tag; <code>UString</code> support.
<code>Connection *getAnyTaggedConnection( const string &amp;username, const string &amp;password, const string &amp;tag="")=0;</code>	Returns a pointer to the connection object from a heterogeneous stateless connection pool, without the restriction of a matching tag; <code>string</code> support.
<code>Connection* getAnyTaggedConnection( const UString &amp;userName, const UString &amp;Password, const UString &amp;tag)=0 ;</code>	Returns a pointer to the connection object from a heterogeneous stateless connection pool, without the restriction of a matching tag; <code>UString</code> support.

Parameter	Description
userName	The database username
password	The database password.
tag	User-defined type of connection requested. This parameter can be ignored if a default connection is requested.

## getAnyTaggedProxyConnection()

Returns a proxy connection from a connection pool.

This method works in an environment with enabled database resident connection pooling.

During the execution of this call, the pool is first searched based on the tag provided. If a connection with the specified tag exists, it is returned to the user. If a matching connection is not available, an appropriately authenticated connection with a different tag is returned. In cases where an undated connection is not free, an appropriately authenticated connection with a different tag is returned.

Restrictions for matching the tag may be removed by passing an empty tag argument parameter.

A `getTag()` call to the connection verifies the connection tag received.

Syntax	Description
<pre>Connection *getAnyTaggedProxyConnection(     const string &amp;name,     string roles[],     unsigned int numRoles,     const string tag="",     Connection::ProxyType         proxyType=Connection::PROXY_DEFAULT);</pre>	Get a proxy connection with role specifications from a connection pool; includes support for roles and string support.
<pre>Connection* getAnyTaggedProxyConnection(     const UString &amp;name,     string roles[],     unsigned int numRoles,     const UString &amp;tag,     Connection::ProxyType         proxyType = Connection::PROXY_DEFAULT);</pre>	Get a proxy connection with role specifications from a connection pool; includes support for roles and UString support.
<pre>Connection *getAnyTaggedProxyConnection(     const string &amp;name,     const string tag="",     Connection::ProxyType         proxyType=Connection::PROXY_DEFAULT);</pre>	Get a proxy connection with role specifications from a connection pool; string support.
<pre>Connection* getAnyTaggedProxyConnection(     const UString &amp;name,     const UString &amp;tag,     Connection::ProxyType         proxyType = Connection::PROXY_DEFAULT);</pre>	Get a proxy connection within role specifications from the connection pool; UString support.

Parameter	Description
name	The username.

Parameter	Description
roles	The roles to activate on the database server
numRoles	The number of roles to activate on the database server
tag	User defined tag associated with the connection.
proxyType	The type of proxy authentication to perform; ProxyType is defined in <a href="#">Table 13-11</a> on page 13-48.

## getBusyConnections()

Returns the number of busy connections in the connection pool. When using database resident connection pooling, this is the number of persistent connections to the Connection Broker.

### Syntax

```
unsigned int getBusyConnections() const=0;
```

## getBusyOption()

Returns the behavior of the stateless connection pool when all the connections in the pool are busy, and when the number of connections have reached maximum. The return values are defined for BusyOption in [Table 13-40](#) on page 13-202.

### Syntax

```
BusyOption getBusyOption()=0;
```

## getConnection()

Returns a pointer to the connection object of a StatelessConnectionPool.

This method works in an environment with enabled database resident connection pooling.

Syntax	Description
Connection *getConnection( string &tag="")=0;	Returns an authenticated connection, with a connection pool username and password; string support.
Connection* getConnection( const UString &tag)=0;	Returns an authenticated connection, with a connection pool username and password; UString support.
Connection *getConnection( const string &userName, const string &password, const string &tag="")=0;	Returns a pointer to the connection object from a heterogeneous stateless connection pool; string support.
Connection* getConnection( const UString &userName, const UString &password, const UString &tag)=0;	Returns a pointer to the connection object from a heterogeneous stateless connection pool; UString support.

Syntax	Description
<pre>Connection *getConnection(     const string &amp;connectionClass,     const Connection::Purity &amp;purity)=0;</pre>	Returns a pointer to the connection object from a database resident connection pool; string support.
<pre>Connection* getConnection(     const UString &amp;connectionClass,     const Connection::Purity &amp;purity)=0;</pre>	Returns a pointer to the connection object from a database resident connection pool; UString support.
<pre>Connection *getConnection(     const string &amp;userName,     const string &amp;password,     const string &amp;connectionClass,     const Connection::Purity &amp;purity)=0;</pre>	Returns a pointer to the connection object from a database resident connection pool; user name and password authentication; string support.
<pre>Connection* getConnection(     const UString &amp;userName,     const UString &amp;password,     const UString &amp;connectionClass,     const Connection::Purity &amp;purity)=0;</pre>	Returns a pointer to the connection object from a database resident connection pool; user name and password authentication; UString support.
<pre>Connection *getConnection(     const string &amp;connectionClass,     const Connection::Purity &amp;purity,     const string &amp;tag)=0;</pre>	Returns a tagged connection object from a database resident connection pool; string support.
<pre>Connection* getConnection(     const UString &amp;connectionClass,     const Connection::Purity &amp;purity,     const UString &amp;tag)=0;</pre>	Returns a tagged connection object from a database resident connection pool; UString support.

Parameter	Description
userName	The database username.
password	The database password.
tag	The user defined tag associated with the connection. During the call, the pool is first searched based on the tag provided. If a connection with the specified tag exists it is returned; otherwise a new connection is created and returned.
connectionClass	The class of connection used by database resident connection pool.
purity	The purity of connection used by database resident connection pool; either SELF or NEW.

## getIncrConnections()

Returns the number of incremental connections in the connection pool. This call is useful only in cases of homogeneous connection pools. When using database resident connection pooling, this is the number of persistent connections to the Connection Broker.

### Syntax

```
unsigned int getIncrConnections() const=0;
```

## getMaxConnections()

Returns the maximum number of connections in the connection pool. When using database resident connection pooling, this is the number of persistent connections to the Connection Broker.

### Syntax

```
unsigned int getMaxConnections() const=0;
```

## getMinConnections()

Returns the minimum number of connections in the connection pool. When using database resident connection pooling, this is the number of persistent connections to the Connection Broker.

### Syntax

```
unsigned int getMinConnections() const=0;
```

## getOpenConnections()

Returns the number of open connections in the connection pool. When using database resident connection pooling, this is the number of persistent connections to the Connection Broker.

### Syntax

```
unsigned int getOpenConnections() const=0;
```

## getPoolName()

Returns the name of the connection pool.

### Syntax

```
string getPoolName() const=0;
```

## getProxyConnection()

Returns a proxy connection from a connection pool.

This method works in an environment with enabled database resident connection pooling.

Syntax	Description
<pre>Connection *getProxyConnection(     const string &amp;userName,     string roles[],     unsigned int numRoles,     const string&amp; tag="",     Connection::ProxyType     proxyType=Connection::PROXY_DEFAULT)=0;</pre>	<p>Get a proxy connection with role specifications from a connection pool; support for roles and string support.</p>

Syntax	Description
<pre>Connection* getProxyConnection(     const UString &amp;userName,     UString roles[],     unsigned int numRoles,     const UString &amp;tag,     Connection::ProxyType         proxyType = Connection::PROXY_DEFAULT);</pre>	Get a proxy connection with role specifications from a connection pool; support for roles and UString support.
<pre>Connection *getProxyConnection(     const string &amp;userName,     const string &amp;connectionClass,     const Connection::Purity &amp;purity)=0;</pre>	Get a proxy connection from a database resident connection pool; string support.
<pre>Connection *getProxyConnection(     const UString &amp;userName,     const UString &amp;connectionClass,     const Connection::Purity &amp;purity)=0;</pre>	Get a proxy connection from a database resident connection pool; UString support.
<pre>Connection *getProxyConnection(     const string &amp;userName,     string roles[],     unsigned int numRoles,     const string &amp;connectionClass,     const Connection::Purity &amp;purity)=0;</pre>	Get a proxy connection with role specifications from a connection pool; support for roles and database resident connection pooling; string support.
<pre>Connection* getProxyConnection(     const UString &amp;userName,     UString roles[],     unsigned int numRoles,     const UString &amp;connectionClass,     const Connection::Purity &amp;purity)=0;</pre>	Get a proxy connection with role specifications from a connection pool; support for roles and database resident connection pooling; UString support.
<pre>Connection *getProxyConnection(     const string &amp;userName,     const string&amp; tag="",     Connection::ProxyType         proxyType=Connection::PROXY_DEFAULT)=0;</pre>	Get a proxy connection without role specifications from a connection pool; string support.
<pre>Connection* getProxyConnection(     const UString &amp;userName,     const UString &amp;tag,     Connection::ProxyType         proxyType = Connection::PROXY_DEFAULT)</pre>	Get a proxy connection without role specifications from a connection pool; UString support.

Parameter	Description
userName	The user name.
roles	The roles to activate on the database server.
numRoles	The number of roles to activate on the database server.
tag	The user defined tag associated with the connection. During the execution of this call, the pool is first searched based on the tag provided. If a connection with the specified tag exists it is returned; otherwise, a new connection is created and returned.
proxyType	The type of proxy authentication to perform; ProxyType is defined in <a href="#">Table 13–11</a> on page 13-48.
connectionClass	The class of connection used by database resident connection pool.



Parameter	Description
<code>purity</code>	The purity of connection used by database resident connection pool; either <code>SELF</code> or <code>NEW</code> .

## getStmtCacheSize()

Retrieves the size of the statement cache.

### Syntax

```
unsigned int getStmtCacheSize() const=0;
```

## getTimeout()

Returns the timeout period of a connection in the connection pool.

### Syntax

```
unsigned int getTimeout() const=0;
```

## releaseConnection()

Releases the connection back to the pool with an optional tag.

This method works in an environment with enabled database resident connection pooling.

Syntax	Description
<pre>void releaseConnection(     Connection *connection,     const string&amp; tag="");</pre>	Support for <code>string</code> tag.
<pre>void releaseConnection(     Connection *connection,     const UString &amp;tag);</pre>	Support for <code>UString</code> tag.

Parameter	Description
<code>connection</code>	The connection to be released.
<code>tag</code>	The user defined tag associated with the connection. The default of this parameter is " ", which untags the connection.

## setBusyOption()

Specifies the behavior of the stateless connection pool when all the connections in the pool are busy, and when the number of connections have reached maximum.

### Syntax

```
void setBusyOption(
```

```
BusyOption busyOption)=0;
```

Parameter	Description
busyOption	Valid values are defined in <code>BusyOption</code> in <a href="#">Table 13-40</a> on page 13-202.

## setPoolSize()

Sets the maximum, minimum, and incremental number of pooled connections for the connection pool.

### Syntax

```
void setPoolSize(
    unsigned int maxConn=1,
    unsigned int minConn=0,
    unsigned int incrConn=1)=0;
```

Parameter	Description
maxConn	The maximum number of connections in the connection pool.
minConn	The minimum number of connections, in homogeneous pools only.
incrConn	The incremental number of connections, in homogeneous pools only.

## setTimeout()

Sets the time out period of a connection in the connection pool. OCI will terminate any connections related to this connection pool that have been idle for longer than the time out period specified.

If this attribute is not set, the least recently used connection will be timed out when pool space is required. Oracle only checks for timed out connections when it releases a connection back to the pool.

### Syntax

```
void setTimeout(
    unsigned int connTimeOut=0)=0;
```

Parameter	Description
connTimeOut	The time out period, given in seconds.

## setStmtCacheSize()

Enables or disables statement caching. A nonzero value will enable statement caching, with a cache of specified size. A zero value will disable caching.

If the user changes the cache size of individual connections and subsequently returns the connection back to the pool with a tag, the cache size does not revert to the one set

---

for the pool. If the connection is untagged, the cache size is reset to equal the cache size specified for the pool.

**Syntax**

```
void setStmtCacheSize(  
    unsigned int cacheSize)=0;
```

Parameter	Description
cacheSize	The size of the statement cache

**terminateConnection()**

Closes the connection and removes it from the pool.

This method works in an environment with enabled database resident connection pooling.

**Syntax**

```
void terminateConnection(  
    Connection *connection)=0;
```

Parameter	Description
connection	The connection to be terminated

## Statement Class

A `Statement` object is used for executing SQL statements. The statement may be a query returning result set, or a non-query statement returning an update count. Non-query SQL can be insert, update, or delete statements. Non-query SQL statements can also be DML statements (such as create, grant, and so on) or stored procedure calls.

A query, insert / update / delete, or stored procedure call statements may have `IN` bind parameters, while a stored procedure call statement may have either `OUT` bind parameters or bind parameters that are both `IN` and `OUT`, referred to as `IN/OUT` parameters.

The `Statement` class methods are divided into three categories:

- Statement methods applicable to all statements
- Methods applicable to prepared statements with `IN` bind parameters
- Methods applicable to callable statements with `OUT` or `IN/OUT` bind parameters.

**Table 13–42 Enumerated Values used by the Statement Class**

Attribute	Options
Status	<ul style="list-style-type: none"> <li>■ <code>NEEDS_STREAM_DATA</code> indicates that output Streams must be written for the streamed <code>IN</code> bind parameters. If there is more than one streamed parameter, call the <code>getCurrentStreamParam()</code> method to find out the bind parameter needing the stream. If the statement is executed iteratively, call <code>getCurrentIteration()</code> to find the iteration for which stream needs to be written.</li> <li>■ <code>PREPARED</code> indicates that the <code>Statement</code> is set to a query.</li> <li>■ <code>RESULT_SET_AVAILABLE</code> indicates that the <code>getResultSet()</code> method must be called to get the result set.</li> <li>■ <code>STREAM_DATA_AVAILABLE</code> indicates that the input Streams must be read for the streamed <code>OUT</code> bind parameters. If there is more than one streamed parameter, call the <code>getCurrentStreamParam()</code> method to find out the bind parameter needing the stream. If the statement is executed iteratively, call <code>getCurrentIteration()</code> to find the iteration for which stream needs to be read.</li> <li>■ <code>UPREPARED</code> indicates that the <code>Statement</code> object is not set to a query.</li> <li>■ <code>UPDATE_COUNT_AVAILABLE</code> indicates that the <code>getUpdateCount()</code> method must be called to find out the update count.</li> </ul>

**Table 13–43 Statement Methods**

Method	Description
<code>addIteration()</code> on page 13-216	Adds an iteration for execution.
<code>closeResultSet()</code> on page 13-216	Immediately releases a result set's database and OCCI resources instead of waiting for automatic release.
<code>closeStream()</code> on page 13-216	Closes the stream specified by the parameter <code>stream</code> .
<code>disableCaching()</code> on page 13-216	Disables statement caching.
<code>execute()</code> on page 13-217	Runs the SQL statement.
<code>executeArrayUpdate()</code> on page 13-217	Runs insert, update, and delete statements that use only the <code>setDataBuffer()</code> or stream interface for bind parameters.

**Table 13–43 (Cont.) Statement Methods**

Method	Description
<a href="#">executeQuery()</a> on page 13-218	Runs a SQL statement that returns a single <code>ResultSet</code> .
<a href="#">executeUpdate()</a> on page 13-218	Runs a SQL statement that does not return a <code>ResultSet</code> .
<a href="#">getAutoCommit()</a> on page 13-218	Returns the current auto-commit state.
<a href="#">getBatchErrorMode()</a> on page 13-218	Returns the state of the batch error mode.
<a href="#">getBDouble()</a> on page 13-219	Returns the value of an IEEE754 <code>DOUBLE</code> as a <code>BDouble</code> object.
<a href="#">getBfile()</a> on page 13-219	Returns the value of a <code>BFILE</code> as a <code>Bfile</code> object.
<a href="#">getBFloat()</a> on page 13-219	Returns the value of a IEEE754 <code>FLOAT</code> as a <code>BFloat</code> object.
<a href="#">getBlob()</a> on page 13-219	Returns the value of a <code>BLOB</code> as a <code>Blob</code> object.
<a href="#">getBytes()</a> on page 13-220	Returns the value of a SQL <code>BINARY</code> or <code>VARBINARY</code> parameter as <code>Bytes</code> .
<a href="#">getCharSet()</a> on page 13-220	Returns the character set that is in effect for the specified parameter, as a <code>string</code> .
<a href="#">getCharSetUString()</a> on page 13-220	Returns the character set that is in effect for the specified parameter, as a <code>UString</code> .
<a href="#">getClob()</a> on page 13-220	Returns the value of a <code>CLOB</code> as a <code>Clob</code> object.
<a href="#">getConnection()</a> on page 13-221	Returns the connection from which the <code>Statement</code> object was instantiated.
<a href="#">getCurrentIteration()</a> on page 13-221	Returns the iteration number of the current iteration that is being processed.
<a href="#">getCurrentStreamIteration()</a> on page 13-221	Returns the current iteration for which stream data is to be read or written.
<a href="#">getCurrentStreamParam()</a> on page 13-221	Returns the parameter index of the current output <code>Stream</code> that must be read or written.
<a href="#">getCursor()</a> on page 13-221	Returns the <code>REF CURSOR</code> value of an <code>OUT</code> parameter as a <code>ResultSet</code> .
<a href="#">getDatabaseNCHARParam()</a> on page 13-222	Returns whether data is in <code>NCHAR</code> character set.
<a href="#">getDate()</a> on page 13-222	Returns the value of a parameter as a <code>Date</code> object.
<a href="#">getBDouble()</a> on page 13-219	Returns the value of a parameter as an IEEE754 double.
<a href="#">getDouble()</a> on page 13-222	Returns the value of a parameter as a C++ double.
<a href="#">getBFloat()</a> on page 13-219	Returns the value of a parameter as an IEEE754 float.
<a href="#">getFloat()</a> on page 13-223	Returns the value of a parameter as a C++ float.
<a href="#">getInt()</a> on page 13-223	Returns the value of a parameter as a C++ int.
<a href="#">getIntervalDS()</a> on page 13-223	Returns the value of a parameter as a <code>IntervalDS</code> object.
<a href="#">getIntervalYM()</a> on page 13-223	Returns the value of a parameter as a <code>IntervalYM</code> object.
<a href="#">getMaxIterations()</a> on page 13-224	Returns the current limit on maximum number of iterations.
<a href="#">getMaxParamSize()</a> on page 13-224	Returns the current max parameter size limit.
<a href="#">getNumber()</a> on page 13-224	Returns the value of a parameter as a <code>Number</code> object.

**Table 13–43 (Cont.) Statement Methods**

<b>Method</b>	<b>Description</b>
<a href="#">getObject()</a> on page 13-224	Returns the value of a parameter as a <code>PObject</code> .
<a href="#">getOCIStatement()</a> on page 13-225	Returns the OCI statement handle associated with the <code>Statement</code> .
<a href="#">getRef()</a> on page 13-225	Returns the value of a REF parameter as <code>RefAny</code> .
<a href="#">getResultSet()</a> on page 13-225	Returns the current result as a <code>ResultSet</code> .
<a href="#">getRowid()</a> on page 13-225	Returns the row id parameter value as a <code>Bytes</code> object.
<a href="#">getSQL()</a> on page 13-225	Returns the current SQL string associated with the <code>Statement</code> object.
<a href="#">getSQLUString()</a> on page 13-226	Returns the current SQL string associated with the <code>Statement</code> object; globalization enabled.
<a href="#">getStream()</a> on page 13-226	Returns the value of the parameter as a stream.
<a href="#">getString()</a> on page 13-226	Returns the value of the parameter as a string.
<a href="#">getTimestamp()</a> on page 13-226	Returns the value of the parameter as a <code>Timestamp</code> object.
<a href="#">getUInt()</a> on page 13-227	Returns the value of the parameter as a C++ unsigned int.
<a href="#">getUpdateCount()</a> on page 13-227	Returns the current result as an update count for non-query statements.
<a href="#">getUString()</a> on page 13-227	Returns the value of a <code>UString</code> .
<a href="#">getVector()</a> on page 13-227	Returns the specified parameter as a vector.
<a href="#">getVectorOfRefs()</a> on page 13-229	Returns the column in the current position as a vector of REFS.
<a href="#">isNull()</a> on page 13-230	Checks whether the parameter is <code>NULL</code> .
<a href="#">isTruncated()</a> on page 13-230	Checks whether the value is truncated.
<a href="#">preTruncationLength()</a> on page 13-230	Returns the actual length of the parameter before truncation.
<a href="#">registerOutParam()</a> on page 13-231	Registers the type and max size of the OUT parameter.
<a href="#">setAutoCommit()</a> on page 13-232	Specifies auto commit mode.
<a href="#">setBatchErrorMode()</a> on page 13-232	Enables or disables the batch error processing mode.
<a href="#">setBDouble()</a> on page 13-232	Sets a parameter to an IEEE double value.
<a href="#">setBfile()</a> on page 13-232	Sets a parameter to a <code>Bfile</code> value.
<a href="#">setBFloat()</a> on page 13-233	Sets a parameter to an IEEE float value.
<a href="#">setBinaryStreamMode()</a> on page 13-233	Specifies that a column is to be returned as a binary stream.
<a href="#">setBlob()</a> on page 13-233	Sets a parameter to a <code>Blob</code> value.
<a href="#">setBytes()</a> on page 13-234	Sets a parameter to a <code>Bytes</code> array.
<a href="#">setCharacterStreamMode()</a> on page 13-234	Specifies that a column is to be returned as a character stream.
<a href="#">setCharSet()</a> on page 13-234	Specifies the character set as a string.
<a href="#">setCharSetUString()</a> on page 13-235	Specifies the character set as a <code>UString</code> .
<a href="#">setClob()</a> on page 13-235	Sets a parameter to a <code>Clob</code> value.

**Table 13–43 (Cont.) Statement Methods**

<b>Method</b>	<b>Description</b>
<a href="#">setDate()</a> on page 13-235	Sets a parameter to a <code>Date</code> value.
<a href="#">setDatabaseNCHARParam()</a> on page 13-236	Sets to true if the data is to be in the NCHAR character set of the database; set to false to restore the default.
<a href="#">setDataBuffer()</a> on page 13-236	Specifies a data buffer where data would be available for reading or writing.
<a href="#">setDataBufferArray()</a> on page 13-237	Specifies an array of data buffers where data would be available for reading or writing.
<a href="#">setDouble()</a> on page 13-238	Sets a parameter to a C++ double value.
<a href="#">setErrorOnNull()</a> on page 13-238	Enables Or Disables exceptions for reading of NULL values.
<a href="#">setErrorOnTruncate()</a> on page 13-239	Enables Or Disables exception when truncation occurs.
<a href="#">setFloat()</a> on page 13-239	Sets a parameter to a C++ float value.
<a href="#">setInt()</a> on page 13-239	Sets a parameter to a C++ int value.
<a href="#">setIntervalDS()</a> on page 13-240	Sets a parameter to a <code>IntervalDS</code> value.
<a href="#">setIntervalYM()</a> on page 13-240	Sets a parameter to a <code>IntervalYM</code> value.
<a href="#">setMaxIterations()</a> on page 13-240	Sets the maximum number of invocations that will be made for the DML statement.
<a href="#">setMaxParamSize()</a> on page 13-241	Sets the maximum amount of data that can sent or returned from the parameter.
<a href="#">setNull()</a> on page 13-241	Sets a parameter to SQL NULL.
<a href="#">setNumber()</a> on page 13-242	Sets a parameter to a <code>Number</code> value.
<a href="#">setObject()</a> on page 13-242	Sets the value of a parameter using an object.
<a href="#">setPrefetchMemorySize()</a> on page 13-242	Sets the amount of memory that will be used internally by OCCI to store data fetched during each round trip to the server.
<a href="#">setPrefetchRowCount()</a> on page 13-243	Sets the number of rows that will be fetched internally by OCCI during each round trip to the server.
<a href="#">setRef()</a> on page 13-243	Sets the value of a parameter to a reference.
<a href="#">setRowid()</a> on page 13-243	Sets a row id bytes array for a bind position.
<a href="#">setSQL()</a> on page 13-244	Associates new SQL string with <code>Statement</code> object.
<a href="#">setSQLUString()</a> on page 13-244	Associates new SQL string with <code>Statement</code> object; globalization enabled.
<a href="#">setString()</a> on page 13-244	Sets a parameter for a specified index.
<a href="#">setTimestamp()</a> on page 13-245	Sets a parameter to a <code>Timestamp</code> value.
<a href="#">setUInt()</a> on page 13-245	Sets a parameter to a C++ unsigned int value.
<a href="#">setUString()</a> on page 13-245	Sets a parameter for a specified index; globalization enabled.
<a href="#">setVector()</a> on page 13-246	Sets a parameter to a vector of unsigned int.
<a href="#">setVectorOfRefs()</a> on page 13-251	Sets a parameter to a vector; should be used when the type is a collection of <code>REFs</code> .
<a href="#">status()</a> on page 13-252	Returns the current status of the statement. This is useful when there is streamed data to be written.

## addIteration()

After specifying set parameters, an iteration is added for execution.

### Syntax

```
void addIteration();
```

## closeResultSet()

Immediately releases the specified `resultSet`'s database and OCI resources when the result set is not needed.

### Syntax

```
void closeResultSet(  
    ResultSet *resultSet);
```

Parameter	Description
<code>resultSet</code>	The result set to be closed; may be a result of <a href="#">getResultSet()</a> , <a href="#">executeQuery()</a> , or <a href="#">getCursor()</a> calls on the current statement, or by a <a href="#">getCursor()</a> call of another result set on the same statement.

## closeStream()

Closes the stream specified by the parameter `stream`.

### Syntax

```
void closeStream(  
    Stream *stream);
```

Parameter	Description
<code>stream</code>	The stream to be closed.

## disableCaching()

Disables statement caching. Used if a user wishes to destroy a statement instead of caching it. Effective only if statement caching is enabled.

### Syntax

```
void disableCaching();
```

## execute()

Executes an SQL statement that may return either a result set or an update count. The statement may have read-able streams which may have to be written, in which case the results of the execution may not be readily available. The returned value `Status` is defined in [Table 13-42](#) on page 13-212.



If output streams are used for OUT bind variables, they must be completely read in order. The `getCurrentStreamParam()` method would indicate which stream needs to be read. Similarly, `getCurrentIteration()` would indicate the iteration for which data is available.

Syntax	Description
<code>Status execute(     const string &amp;sql="");</code>	Executes the SQL Statement.
<code>Status execute(     const UString &amp;sql);</code>	Executes the SQL Statement; globalization enabled.

Parameter	Description
<code>sql</code>	The SQL statement to be executed. This can be NULL if the <code>executeArrayUpdate()</code> method was used to associate the sql with the statement.

## executeArrayUpdate()

Executes insert/update/delete statements which use only the `setDataBuffer()` or stream interface for bind parameters. The bind parameters must be arrays of size `arrayLength` parameter. The statement may have writeable streams which may have to be written. The returned value `Status` is defined in [Table 13-42](#) on page 13-212.

If output streams are used for OUT bind variables, they must be completely read in order. The `getCurrentStreamParam()` method would indicate which stream needs to be read. Similarly, `getCurrentIteration()` would indicate the iteration for which data is available.

---

**Note:** You cannot perform array executes for queries or callable statements.

---

### Syntax

```
Status executeArrayUpdate(  
    unsigned int arrayLength);
```

Parameter	Description
<code>arrayLength</code>	The number of elements provided in each buffer of bind variables.

## executeQuery()

Runs a SQL statement that returns a `ResultSet`. Should not be called for a statement which is not a query, has streamed parameters. Returns a `ResultSet` that contains the data produced by the query.

Syntax	Description
<code>ResultSet* executeQuery(const string &amp;sql="");</code>	Executes the SQL Statement that returns a <code>ResultSet</code> .
<code>ResultSet* executeQuery(const UString &amp;sql);</code>	Executes the SQL Statement that returns a <code>ResultSet</code> ; globalization enabled.

Parameter	Description
sql	The SQL statement to be executed. This can be NULL if the <a href="#">executeArrayUpdate()</a> method was used to associate the sql with the statement.

## executeUpdate()

Executes a non-query statement such as a SQL INSERT, UPDATE, DELETE statement, a DDL statement such as CREATE/ALTER and so on, or a stored procedure call. Returns either the row count for INSERT, UPDATE or DELETE or 0 for SQL statements that return nothing.

Syntax	Description
<code>unsigned int executeUpdate(const string &amp;sql="");</code>	Executes a non-query statement.
<code>unsigned int executeUpdate(const UString &amp;sql);</code>	Executes a non-query statement; globalization enabled.

Parameter	Description
sql	The SQL statement to be executed. This can be NULL if the <a href="#">executeArrayUpdate()</a> method was used to associate the sql with the statement.

## getAutoCommit()

Returns the current auto-commit state.

### Syntax

```
bool getAutoCommit() const;
```

## getBatchErrorMode()

Returns the state of the batch error mode; TRUE if the batch error mode is enabled, FALSE otherwise.

### Syntax

```
bool getBatchErrorMode() const;
```

## getBDouble()

Returns the value of an IEEE754 DOUBLE column, which has been defined as an OUT bind. If the value is SQL NULL, the result is 0.

### Syntax

```
BDouble getBDouble(
    unsigned int paramIndex) = 0;
```

Parameter	Description
paramIndex	Parameter index; first parameter is 1, second is 2, and so on.

## getBfile()

Returns the value of a BFILE parameter as a Bfile object.

### Syntax

```
Bfile getBfile(
    unsigned int paramIndex);
```

Parameter	Description
paramIndex	Parameter index; first parameter is 1, second is 2, and so on.

## getBFloat()

Gets the value of an IEEE754 FLOAT column, which has been defined as an OUT bind. If the value is SQL NULL, the result is 0.

### Syntax

```
BFloat getBFloat(
    unsigned int paramIndex) = 0;
```

Parameter	Description
paramIndex	Parameter index; first parameter is 1, second is 2, and so on.

## getBlob()

Returns the value of a BLOB parameter as a Blob.

### Syntax

```
Blob getBlob(
    unsigned int paramIndex);
```

Parameter	Description
paramIndex	Parameter index; first parameter is 1, second is 2, and so on.

## getBytes()

Returns the value of n SQL `BINARY` or `VARBINARY` parameter as `Bytes`; if the value is SQL `NULL`, the result is `NULL`.

### Syntax

```
Bytes getBytes(  
    unsigned int paramIndex);
```

Parameter	Description
paramIndex	Parameter index; first parameter is 1, second is 2, and so on.

## getCharSet()

Returns the character set that is in effect for the specified parameter, as a `string`.

### Syntax

```
string getCharSet(  
    unsigned int paramIndex) const;
```

Parameter	Description
paramIndex	Parameter index; first parameter is 1, second is 2, and so on.

## getCharSetUString()

Returns the character set that is in effect for the specified parameter, as a `UString`.

### Syntax

```
UString getCharSetUString(  
    unsigned int paramIndex) const;
```

Parameter	Description
paramIndex	Parameter index; first parameter is 1, second is 2, and so on.

## getClob()

Get the value of a `CLOB` parameter as a `Clob`. Returns the parameter value.

### Syntax

```
Clob getClob(  
    unsigned int paramIndex);
```

Parameter	Description
paramIndex	Parameter index; first parameter is 1, second is 2, and so on.

## getConnection()

Returns the connection from which the `Statement` object was instantiated.

### Syntax

```
Connection* getConnection() const;
```

## getCurrentIteration()

If the prepared statement has any output `Streams`, this method returns the current iteration of the statement that is being processed by OCCI. If this method is called after all the invocations in the set of iterations has been processed, it returns 0. Returns the iteration number of the current iteration that is being processed. The first iteration is numbered 1 and so on. If the statement has finished execution, a 0 is returned.

### Syntax

```
unsigned int getCurrentIteration() const;
```

## getCurrentStreamIteration()

Returns the current parameter stream for which data is available.

### Syntax

```
unsigned int getCurrentStreamIteration() const;
```

## getCurrentStreamParam()

Returns the parameter index of the current output `Stream` parameter that must be written. If the prepared statement has any output `Stream` parameters, this method returns the parameter index of the current output `Stream` that must be written. If no output `Stream` needs to be written, or there are no output `Stream` parameters in the prepared statement, this method returns 0.

### Syntax

```
unsigned int getCurrentStreamParam() const;
```

## getCursor()

Gets the `REF CURSOR` value of an `OUT` parameter as a `ResultSet`. Data can be fetched from this result set. The `OUT` parameter must be registered as `CURSOR` with the [registerOutParam\(\)](#) method. Returns a `ResultSet` for the `OUT` parameter value.

---

**Note:** If there are multiple `REF CURSOR`s being returned due to a batched call, data from each cursor must be completely fetched before retrieving the next `REF CURSOR` and starting fetch on it.

---

### Syntax

```
ResultSet * getCursor(
```

```
unsigned int paramIndex);
```

Parameter	Description
paramIndex	Parameter index; first parameter is 1, second is 2, and so on.

## getDatabaseNCHARParam()

Returns whether data is in NCHAR character set or not.

### Syntax

```
bool getDatabaseNCHARParam(  
    unsigned int paramIndex) const;
```

Parameter	Description
paramIndex	Parameter index; first parameter is 1, second is 2, and so on.

## getDate()

Get the value of a SQL DATE parameter as a Date object. Returns the parameter value; if the value is SQL NULL, the result is NULL.

### Syntax

```
Date getDate(  
    unsigned int paramIndex) const;
```

Parameter	Description
paramIndex	Parameter index; first parameter is 1, second is 2, and so on.

## getDouble()

Get the value of a DOUBLE parameter as a C++ double. Returns the parameter value; if the value is SQL NULL, the result is 0.

### Syntax

```
double getDouble(  
    unsigned int paramIndex);
```

Parameter	Description
paramIndex	Parameter index; first parameter is 1, second is 2, and so on.

## getFloat()

Get the value of a FLOAT parameter as a C++ float. Returns the parameter value; if the value is SQL NULL, the result is 0.

**Syntax**

```
float getFloat(
    unsigned int paramIndex);
```

Parameter	Description
paramIndex	Parameter index; first parameter is 1, second is 2, and so on.

**getInt()**

Get the value of an `INTEGER` parameter as a C++ int. Returns the parameter value; if the value is `SQL NULL`, the result is 0.

**Syntax**

```
unsigned int getInt(
    unsigned int paramIndex);
```

Parameter	Description
paramIndex	Parameter index; first parameter is 1, second is 2, and so on.

**getIntervalDS()**

Get the value of a parameter as a `IntervalDS` object.

**Syntax**

```
IntervalDS getIntervalDS(
    unsigned int paramIndex);
```

Parameter	Description
paramIndex	Parameter index; first parameter is 1, second is 2, and so on.

**getIntervalYM()**

Get the value of a parameter as a `IntervalYM` object.

**Syntax**

```
IntervalYM getIntervalYM(
    unsigned int paramIndex);
```

Parameter	Description
paramIndex	Parameter index; first parameter is 1, second is 2, and so on.

**getMaxIterations()**

Gets the current limit on maximum number of iterations. Default is 1. Returns the current maximum number of iterations.

**Syntax**

```
unsigned int getMaxIterations() const;
```

**getMaxParamSize()**

The `maxParamSize` limit (in bytes) is the maximum amount of data sent or returned for any parameter value; it only applies to character and binary types. If the limit is exceeded, the excess data is silently discarded. Returns the current max parameter size limit.

**Syntax**

```
unsigned int getMaxParamSize(  
    unsigned int paramIndex) const;
```

Parameter	Description
<code>paramIndex</code>	Parameter index; first parameter is 1, second is 2, and so on.

**getNumber()**

Gets the value of a NUMERIC parameter as a `Number` object. Returns the parameter value; if the value is SQL NULL, the result is NULL.

**Syntax**

```
Number getNumber(  
    unsigned int paramIndex);
```

Parameter	Description
<code>paramIndex</code>	Parameter index; first parameter is 1, second is 2, and so on.

**getObject()**

Gets the value of a parameter as a `PObject`. This method returns an `PObject` whose type corresponds to the SQL type that was registered for this parameter using [registerOutParam\(\)](#). Returns A `PObject` holding the OUT parameter value.

---

**Note:** This method may be used to read database-specific, abstract data types.

---

**Syntax**

```
PObject * getObject(  
    unsigned int paramIndex);
```

Parameter	Description
<code>paramIndex</code>	Parameter index; first parameter is 1, second is 2, and so on.



## getOCIStatement()

Get the OCI statement handle associated with the Statement.

### Syntax

```
OCIStmt * getOCIStatement() const;
```

## getRef()

Get the value of a REF parameter as RefAny. Returns the parameter value.

### Syntax

```
RefAny getRef(
    unsigned int paramIndex);
```

Parameter	Description
paramIndex	Parameter index; first parameter is 1, second is 2, and so on.

## getResultSet()

Returns the current result as a ResultSet.

### Syntax

```
ResultSet * getResultSet();
```

## getRowid()

Get the rowid parameter value as a Bytes.

### Syntax

```
Bytes getRowid(
    unsigned int paramIndex);
```

Parameter	Description
paramIndex	Parameter index; first parameter is 1, second is 2, and so on.

## getSQL()

Returns the current SQL string associated with the Statement object.

### Syntax

```
string getSQL() const;
```

## getSQLUString()

Returns the current SQL UString associated with the Statement object; globalization enabled.

### Syntax

```
UString getSQLUString() const;
```

## getStream()

Returns the value of the parameter as a stream.

### Syntax

```
Stream * getStream(  
    unsigned int paramIndex);
```

Parameter	Description
paramIndex	Parameter index; first parameter is 1, second is 2, and so on.

## getString()

Get the value of a CHAR, VARCHAR, or LONGVARCHAR parameter as a string. Returns the parameter value; if the value is SQL NULL, the result is empty string.

### Syntax

```
string getString(  
    unsigned int paramIndex);
```

Parameter	Description
paramIndex	Parameter index; first parameter is 1, second is 2, and so on.

## getTimestamp()

Get the value of a SQL TIMESTAMP parameter as a Timestamp object. Returns the parameter value; if the value is SQL NULL, the result is NULL

### Syntax

```
Timestamp getTimestamp(  
    unsigned int paramIndex);
```

Parameter	Description
paramIndex	Parameter index; first parameter is 1, second is 2, and so on.

## getUInt()

Get the value of a `BIGINT` parameter as a C++ unsigned int. Returns the parameter value; if the value is `SQL NULL`, the result is 0.

### Syntax

```
unsigned int getUInt(
    unsigned int paramIndex);
```

Parameter	Description
<code>paramIndex</code>	Parameter index; first parameter is 1, second is 2, and so on.

## getUpdateCount()

Returns the current result as an update count.

### Syntax

```
unsigned int getUpdateCount() const;
```

## getUString()

Returns the value as a `UString`.

---

**Note:** This method should be called only if the environment's character set is UTF16, or if `setCharset()` method has been called to explicitly retrieve UTF16 data.

---

### Syntax

```
UString getUString(
    unsigned int paramIndex);
```

Parameter	Description
<code>paramIndex</code>	Parameter index; first parameter is 1, second is 2, and so on.

## getVector()

Returns the column in the current position as a vector. The column at the position, specified by index, should be a collection type (`varray` or nested table). The SQL type of the elements in the collection should be compatible with the type of the vector.

Syntax	Description
<pre>void getVector(     Statement *stmt,     unsigned int paramIndex,     std::vector&lt;UString&gt; &amp;vect);</pre>	Used for vectors of <code>UString</code> Class; globalization enabled.

Syntax	Description
<pre>void getVector(     Statement *stmt,     unsigned int paramIndex,     vector&lt;BDouble&gt; &amp;vect);</pre>	Used for BDouble vectors.
<pre>void getVector(     Statement *stmt,     unsigned int paramIndex,     vector&lt;BFile&gt; &amp;vect);</pre>	Used for vectors of <a href="#">Bfile Class</a> .
<pre>void getVector(     Statement *stmt,     unsigned int paramIndex,     vector&lt;BFloat&gt; &amp;vect);</pre>	Used for BFloat vectors.
<pre>void getVector(     Statement *stmt,     unsigned int paramIndex,     vector&lt;Blob&gt; &amp;vect);</pre>	Used for vectors of <a href="#">Blob Class</a> .
<pre>void getVector(     Statement *stmt,     unsigned int paramIndex,     vector&lt;Clob&gt; &amp;vect);</pre>	Used for Clob vectors.
<pre>void getVector(     Statement *stmt,     unsigned int paramIndex,     vector&lt;Date&gt; &amp;vect);</pre>	Used for vectors of <a href="#">Date Class</a> .
<pre>void getVector(     Statement *stmt,     unsigned int paramIndex,     vector&lt;double&gt; &amp;vect);</pre>	Used for vectors of double Class.
<pre>void getVector(     Statement *stmt,     unsigned int paramIndex,     vector&lt;float&gt; &amp;vect);</pre>	Used for vectors of float Class.
<pre>void getVector(     Statement *stmt,     unsigned int paramIndex,     vector&lt;int&gt; &amp;vect);</pre>	Used for vectors of int Class.
<pre>void getVector(     Statement *stmt,     unsigned int paramIndex,     vector&lt;IntervalDS&gt; &amp;vect);</pre>	Used for vectors of <a href="#">IntervalDS Class</a> .
<pre>void getVector(     Statement *stmt,     unsigned int paramIndex,     vector&lt;IntervalYM&gt; &amp;vect);</pre>	Used for vectors of <a href="#">IntervalYM Class</a> .
<pre>void getVector(     Statement *stmt,     unsigned int paramIndex,     vector&lt;Number&gt; &amp;vect);</pre>	Used for vectors of <a href="#">Number Class</a> .

Syntax	Description
<pre>void getVector(     Statement *stmt,     unsigned int paramIndex,     vector&lt;RefAny&gt; &amp;vect);</pre>	Used for vectors of <a href="#">RefAny Class</a> .
<pre>void getVector(     Statement *stmt,     unsigned int paramIndex,     vector&lt;string&gt; &amp;vect);</pre>	Used for vectors of <a href="#">string Class</a> .
<pre>void getVector(     Statement *stmt,     unsigned int paramIndex,     vector&lt;T *&gt; &amp;vect);</pre>	Intended for use on platforms where partial ordering of function templates is supported.
<pre>void getVector(     Statement *stmt,     unsigned int paramIndex,     vector&lt;T&gt; &amp;vect);</pre>	Intended for use on platforms where partial ordering of function templates is not supported, such as Windows NT and z/OS. For OUT binds.
<pre>void getVector(     Statement *stmt,     unsigned int paramIndex,     vector&lt;Timestamp&gt; &amp;vect);</pre>	Used for vectors of <a href="#">Timestamp Class</a> .
<pre>void getVector(     Statement *stmt,     unsigned int paramIndex,     vector&lt;u &lt;Ref&lt;T&gt; &gt; &amp;vect);</pre>	Available only on platforms where partial ordering of function templates is supported.
<pre>void getVector(     Statement *stmt,     unsigned int paramIndex,     vector&lt;unsigned int&gt; &amp;vect);</pre>	Used for on vectors of <a href="#">unsigned int Class</a> .

Parameter	Description
stmt	The statement.
paramIndex	Parameter index.
vect	Reference to the vector (OUT parameter) into which the values should be retrieved.

## getVectorOfRefs()

This method returns the column in the current position as a vector of REFS. The column should be a collection type (varray or nested table) of REFS. Used with OUT binds.

### Syntax

```
void getVectorOfRefs(
    Statement *stmt,
    unsigned int colIndex,
    vector< Ref<T> > &vect);
```

Parameter	Description
stmt	The statement object.
colIndex	Column index; first column is 1, second is 2, and so on.
vect	The reference to the vector of REFs (OUT parameter). It is recommended to use <code>getVectorOfRefs()</code> instead of specialized <code>getVector()</code> function for <code>Ref&lt;T&gt;</code> .

## isNull()

An OUT parameter may have the value of SQL NULL; `isNull()` reports whether the last value read has this special value. Note that you must first call `getxxx()` on a parameter to read its value and then call `isNull()` to see if the value was SQL NULL. Returns TRUE if the last parameter read was SQL NULL.

### Syntax

```
bool isNull(
    unsigned int paramIndex ) const;
```

Parameter	Description
paramIndex	Parameter index; first parameter is 1, second is 2, and so on.

## isTruncated()

This method checks whether the value of the parameter is truncated. If the value of the parameter is truncated, then TRUE is returned; otherwise, FALSE is returned.

### Syntax

```
bool isTruncated(
    unsigned int paramIndex) const;
```

Parameter	Description
paramIndex	Parameter index; first parameter is 1, second is 2, and so on.

## preTruncationLength()

Returns the actual length of the parameter before truncation.

### Syntax

```
int preTruncationLength(
    unsigned int paramIndex) const;
```

Parameter	Description
paramIndex	Parameter index; first parameter is 1, second is 2, and so on.

## registerOutParam()

This method registers the type of each out parameter of a PL/SQL stored procedure. Before executing a PL/SQL stored procedure, you must explicitly call this method to register the type of each out parameter. This method should be called for out parameters only. Use the `setxxx()` method for in/out parameters.

- When reading the value of an out parameter, you must use the `getxxx()` method that corresponds to the parameter's registered SQL type. For example, use `getInt` or `getNumber` when `OCCIINT` or `OCCINumber` is the type specified.
- If a PL/SQL stored procedure has an out parameter of type `ROWID`, the type specified in this method should be `OCCISTRING`. The value of the out parameter can then be retrieved by calling the `getString()` method.
- If a PL/SQL stored procedure has an in/out parameter of type `ROWID`, call the methods `setString()` and `getString()` to set the type and retrieve the value of the `IN/OUT` parameter.

Syntax	Description
<pre>void registerOutParam(     unsigned int paramIndex,     Type type,     unsigned int maxSize=0,     const string &amp;sqltype="");</pre>	Registers the type of each out parameter of a PL/SQL stored procedure.
<pre>void registerOutParam(     unsigned int paramIndex,     Type type,     unsigned int maxSize,     const string typName,     const string &amp;schName);</pre>	Registers the type of each out parameter of a PL/SQL stored procedure; <code>string</code> support.
<pre>void registerOutParam(     unsigned int paramIndex,     Type type,     unsigned int maxSize,     const UString &amp;typName,     const UString &amp;schName);</pre>	Registers the type of each out parameter of a PL/SQL stored procedure; globalization enabled, or <code>UString</code> support.

Parameter	Description
<code>paramIndex</code>	Parameter index; first parameter is 1, second is 2, and so on.
<code>type</code>	SQL type code defined by <code>type</code> ; only data types corresponding to OCCI data types such as <code>Date</code> , <code>Bytes</code> , and so on.
<code>maxSize</code>	The maximum size of the retrieved value. For data types of <code>OCCIBYTES</code> and <code>OCCISTRING</code> , <code>maxSize</code> should be greater than 0.
<code>sqltype</code>	The name of the type in the data base (used for types which have been created with <code>CREATE TYPE</code> ).
<code>typName</code>	The name of the type.
<code>schName</code>	The schema name.

## setAutoCommit()

A `Statement` can be in auto-commit mode. In this case any statement executed is also automatically committed. By default, the auto-commit mode is turned-off.

### Syntax

```
void setAutoCommit(  
    bool autoCommit);
```

Parameter	Description
autoCommit	TRUE enables auto-commit; FALSE disables auto-commit.

## setBatchErrorMode()

Enables or disables the batch error processing mode.

### Syntax

```
virtual void setBatchErrorMode(  
    bool batchErrorMode);
```

Parameter	Description
batchErrorMode	TRUE enables batch error processing; FALSE disables batch error processing.

## setBDouble()

Sets an IEEE754 double as a bind value to a `Statement` object at the position specified by `paramIndex` attribute.

### Syntax

```
void setBDouble(  
    unsigned int paramIndex,  
    const BDouble &dval);
```

Parameter	Description
paramIndex	Parameter index; first parameter is 1, second is 2, and so on.
dval	The parameter value.

## setBfile()

Sets a parameter to a `Bfile` value.

### Syntax

```
void setBfile(  
    unsigned int paramIndex,  
    const Bfile &val);
```



Parameter	Description
paramIndex	Parameter index; first parameter is 1, second is 2, and so on.
val	The parameter value.

## setBFloat()

Sets an IEEE754 float as a bind value to a Statement object at the position specified by the paramIndex attribute.

### Syntax

```
void setBFloat(
    unsigned int paramIndex,
    const BFloat &fval);
```

Parameter	Description
paramIndex	Parameter index; first parameter is 1, second is 2, and so on.
fval	The parameter value.

## setBinaryStreamMode()

Defines that a column is to be returned as a binary stream.

Syntax	Description
void setBinaryStreamMode(     unsigned int colIndex,     unsigned int size);	Sets column returned to be a binary stream.
void setBinaryStreamMode(     unsigned int colIndex,     unsigned int size     bool inArg);	Sets column returned to be a binary stream; used when have PL/SQL IN or IN/OUT arguments in the bind position.

Parameter	Description
colIndex	Column index; first column is 1, second is 2, and so on.
size	The amount of data to be read or returned as a binary Stream.
inArg	Pass TRUE if the bind position is a PL/SQL IN or IN/OUT argument

## setBlob()

Sets a parameter to a Blob value.

### Syntax

```
void setBlob(
    unsigned int paramIndex,
    const Blob &val);
```

Parameter	Description
paramIndex	Parameter index; first parameter is 1, second is 2, and so on.
val	The parameter value.

## setBytes()

Sets a parameter to a Bytes array.

### Syntax

```
void setBytes(
    unsigned int paramIndex,
    const Bytes &val);
```

Parameter	Description
paramIndex	Parameter index; first parameter is 1, second is 2, and so on.
val	The parameter value.

## setCharacterStreamMode()

Defines that a column is to be returned as a character stream.

Syntax	Description
void setCharacterStreamMode(     unsigned int colIndex,     unsigned int size);	Sets column returned to be a character stream.
void setCharacterStreamMode(     unsigned int colIndex,     unsigned int size,     bool inArg);	Sets column returned to be a character stream; used when have PL/SQL IN or IN/OUT arguments in the bind position.

Parameter	Description
colIndex	Column index; first column is 1, second is 2, and so on.
size	The amount of data to be read or returned as a character Stream.
inArg	Pass TRUE if the bind position is a PL/SQL IN or IN/OUT argument

## setCharSet()

Overrides the default character set for the specified parameter. Data is assumed to be in the specified character set and is converted to database character set. For OUT binds, this specifies the character set to which database characters are converted to.

### Syntax

```
void setCharSet(
    unsigned int paramIndex,
    string &charSet);
```

Parameter	Description
paramIndex	Parameter index; first parameter is 1, second is 2, and so on.
charSet	Selected character set, as a string.

## setCharSetUString()

Overrides the default character set for the specified parameter. Data is assumed to be in the specified character set and is converted to database character set. For `OUT` binds, this specifies the character set to which database characters are converted to.

### Syntax

```
void setCharSetUString(
    unsigned int paramIndex,
    const UString& charSet);
```

Parameter	Description
paramIndex	Parameter index; first parameter is 1, second is 2, and so on.
charSet	Selected character set, as a <code>UString</code> .

## setClob()

Sets a parameter to a `Clob` value.

### Syntax

```
void setClob(
    unsigned int paramIndex,
    const Clob &val);
```

Parameter	Description
paramIndex	Parameter index; first parameter is 1, second is 2, and so on.
val	The parameter value.

## setDate()

Sets a parameter to a `Date` value.

### Syntax

```
void setDate(
    unsigned int paramIndex,
    const Date &val);
```

Parameter	Description
paramIndex	Parameter index; first parameter is 1, second is 2, and so on.
val	The parameter value.

## setDatabaseNCHARParam()

If the parameter is going to be inserted in a column that contains data in the database's NCHAR character set, then OCI must be informed by passing a TRUE value. A FALSE can be passed to restore the default. Returns returns the character set that is in effect for the specified parameter.

### Syntax

```
void setDatabaseNCHARParam(
    unsigned int paramIndex,
    bool isNCHAR);
```

Parameter	Description
paramIndex	Parameter index; first parameter is 1, second is 2, and so on.
isNCHAR	TRUE if this parameter contains data in Database's NCHAR character set; FALSE otherwise

## setDataBuffer()

Specifies a data buffer where data would be available. Also used for OUT bind parameters of callable statements.

The `buffer` parameter is a pointer to a user allocated data buffer. The current length of data must be specified in the `length` parameter. The amount of data should not exceed the `size` parameter. Finally, `type` is the data type of the data.

Note that not all types can be supplied in the buffer. For example, all OCI allocated types (such as Bytes, Date and so on) cannot be provided by the [setDataBuffer\(\)](#) interface. Similarly, C++ Standard Library strings cannot be provided with the [setDataBuffer\(\)](#) interface either. The `type` can be any of OCI data types such as VARCHAR2, CSTRING, CHARZ and so on.

If [setDataBuffer\(\)](#) is used to specify data for iterative or array executes, it should be called only once in the first iteration only. For subsequent iterations, OCI would assume that data is at `buffer + (i*size)` location where `i` is the iteration number. Similarly the length of the data would be assumed to be at `(length+i)`.

### Syntax

```
void setDataBuffer(
    unsigned int paramIndex,
    void *buffer,
    Type type,
    sb4 size,
    ub2 *length,
    sb2 *ind = NULL,
    ub2 *rc= NULL);
```

Parameter	Description
paramIndex	Parameter index; first parameter is 1, second is 2, and so on.

Parameter	Description
buffer	Pointer to user-allocated buffer. For iterative or array executes, it should have <code>numIterations()</code> size bytes in it. For array fetches, it should have <code>numRows * size</code> bytes in it. For gather or scatter binds and defines, this structure stores the address of <code>OCIIOVec</code> and the number of <code>OCIIOVec</code> elements that start at that address.
type	Type of the data that is provided (or retrieved) in the buffer.
size	Size of the data buffer; for iterative and array executes, it is the size of each element of the data items. For gather or scatter binds and defines, it is the size of the <code>OCIIOVecArray</code> to which the <code>buffer</code> points; the <code>mode</code> must be set to <code>IOVEC</code> .
length	Pointer to the length of data in the buffer; for iterative and array executes, it should be an array of length data for each buffer element; the size of the array should be equal to <code>arrayLength()</code> .
ind	Indicator. For iterative and array executes, an indicator for every buffer element.
rc	Returns code; for iterative and array executes, a return code for every buffer element.

## setDataBufferArray()

Specifies an array of data buffers where data would be available for reading or writing. Used for `IN`, `OUT`, and `IN/OUT` bind parameters for stored procedures which read/write array parameters.

- A stored procedure can have an array of values for `IN`, `IN/OUT`, or `OUT` parameters. In this case, the parameter must be specified using the [setDataBufferArray\(\)](#) method. The array is specified just as for the [setDataBuffer\(\)](#) method for iterative or array executes, but the number of elements in the array is determined by `*arrayLength` parameter.
- For `OUT` and `IN/OUT` parameters, the maximum number of elements in the array is specified by the `arraySize` parameter. Note that for iterative prepared statements, the number of elements in the array is determined by the number of iterations, and for array executes the number of elements in the array is determined by the `arrayLength` parameter of the [executeArrayUpdate\(\)](#) method. However, for array parameters of stored procedures, the number of elements in the array must be specified in the `arrayLength` parameter of the [setDataBufferArray\(\)](#) method because each parameter may have a different size array.
- This is different from prepared statements where for iterative and array executes, the number of elements in the array for each parameter is the same and is determined by the number of iterations of the statement, but a callable statement is executed only once, and each of its parameter can be a varying length array with possibly a different length.

---

**Note:** For `OUT` and `IN/OUT` binds, the number of elements returned in the array is returned in `arrayLength` as well. The client must make sure that it has allocated size `*arraySize` bytes for the `buffer`.

---

**Syntax**

```
void setDataBufferArray(
    unsigned int paramIndex,
    void *buffer,
    Type type,
    ub4 arraySize,
    ub4 *arrayLength,
    sb4 elementSize,
    ub2 *elementLength,
    sb2 *ind = NULL,
    ub2 *rc = NULL);
```

Parameter	Description
paramIndex	Parameter index; first parameter is 1, second is 2, and so on.
buffer	Pointer to user-allocated buffer. It should have <code>size* arraySize</code> bytes in it. For gather or scatter binds and defines, this structure stores the address of <code>OCIIOVec</code> and the number of <code>OCIIOVec</code> elements that start at that address.
type	Type of the data that is provided (or retrieved) in the buffer.
arraySize	Maximum number of elements in the array.
arrayLength	Pointer to number of current elements in the array.
elementSize	Size of the data buffer for each element. For iterative and array executes, it is the size of each element of the data items. When using gather or scatter binds and defines, it is the size of the <code>OCIIOVecArray</code> ; the mode must be set to <code>IOVEC</code> .
elementLength	Pointer to an array of lengths. <code>elementLength[i]</code> has the current length of the <i>i</i> th element of the array.
ind	Pointer to an array of indicators. An indicator for every buffer element.
rcs	Pointer to an array of return codes.

**setDouble()**

Sets a parameter to a C++ double value.

**Syntax**

```
void setDouble(
    unsigned int paramIndex,
    double val);
```

Parameter	Description
paramIndex	Parameter index; first parameter is 1, second is 2, and so on.
val	The parameter value.

**setErrorOnNull()**

Enables/disables exceptions for reading of `NULL` values on `paramIndex` parameter of the statement. If exceptions are enabled, calling a `getxxx()` on `paramIndex` parameter would result in an `SQLException` if the parameter value is `NULL`. This call can also be used to disable exceptions.

**Syntax**

```
void setErrorOnNull(
    unsigned int paramIndex,
    bool causeException);
```

Parameter	Description
paramIndex	Parameter index; first parameter is 1, second is 2, and so on.
causeException	Enable exceptions if TRUE. Disable if FALSE.

**setErrorOnTruncate()**

This method enables/disables exceptions when truncation occurs.

**Syntax**

```
void setErrorOnTruncate(
    unsigned int paramIndex,
    bool causeException);
```

Parameter	Description
paramIndex	Parameter index; first parameter is 1, second is 2, and so on.
causeException	Enable exceptions if TRUE. Disable if FALSE.

**setFloat()**

Sets a parameter to a C++ float value.

**Syntax**

```
void setFloat(
    unsigned int paramIndex,
    float val);
```

Parameter	Description
paramIndex	Parameter index; first parameter is 1, second is 2, and so on.
val	The parameter value.

**setInt()**

Sets a parameter to a C++ int value.

**Syntax**

```
void setInt(
    unsigned int paramIndex,
    int val);
```

Parameter	Description
paramIndex	Parameter index; first parameter is 1, second is 2, and so on.

Parameter	Description
val	The parameter value.

## setIntervalDS()

Sets a parameter to a `IntervalDS` value.

### Syntax

```
void setIntervalDS(  
    unsigned int paramIndex,  
    const IntervalDS &val);
```

Parameter	Description
paramIndex	Parameter index; first parameter is 1, second is 2, and so on.
val	The parameter value.

## setIntervalYM()

Sets a parameter to a `Interval` value.

### Syntax

```
void setIntervalYM(  
    unsigned int paramIndex,  
    const IntervalYM &val);
```

Parameter	Description
paramIndex	Parameter index; first parameter is 1, second is 2, and so on.
val	The parameter value.

## setMaxIterations()

Sets the maximum number of invocations that will be made for the DML statement. This must be called before any parameters are set on the prepared statement. The larger the iterations, the larger the numbers of parameters sent to the server in one round trip. However, a large number causes more memory to be reserved for all the parameters. Note that this is just the maximum limit. Actual number of iterations depends on the number of calls to [addIteration\(\)](#).

### Syntax

```
void setMaxIterations(  
    unsigned int maxIterations);
```

Parameter	Description
maxIterations	Maximum number of iterations allowed on this statement.



## setMaxParamSize()

This method sets the maximum amount of data to be sent or received for the specified parameter. It only applies to character and binary data. If the maximum amount is exceeded, the excess data is discarded. This method can be very useful when working with a LONG column. It can be used to truncate the LONG column by reading or writing it into a string or Bytes data type.

If the `getSQL()` or `setBytes()` method has been called to bind a value to an IN/OUT parameter of a PL/SQL procedure, and the size of the OUT value is expected to be greater than the size of the IN value, then `setMaxParamSize()` should be called.

### Syntax

```
void setMaxParamSize(
    unsigned int paramIndex,
    unsigned int maxSize);
```

Parameter	Description
paramIndex	Parameter index; first parameter is 1, second is 2, and so on.
maxSize	The new maximum parameter size limit; must be >0.

## setNull()

Sets a parameter to SQL NULL. Note that you must specify the parameter's SQL type.

Syntax	Description
<pre>void setNull(     unsigned int paramIndex,     Type type);</pre>	Sets the value of a parameter to NULL using an object.
<pre>void setNull(     unsigned int paramIndex,     Type type,     const string &amp;typeName,     const string &amp;schemaName = "")</pre>	Sets the value of a parameter to NULL for object and collection types, OCCIPOBJECT and OCCIVECTOR. Uses the appropriate schema and type name of the object or collection type. Support for string.
<pre>void setNull(     unsigned int paramIndex,     Type type,     UString &amp;typeName,     UString &amp;schemaName);</pre>	Sets the value of a parameter to NULL for object and collection types, OCCIPOBJECT and OCCIVECTOR. Uses the appropriate schema and type name of the object or collection type. Support for UString.

Parameter	Description
paramIndex	Parameter index; first parameter is 1, second is 2, and so on.
type	SQL type.
typeName	Type name of the object or collection.
schemaName	Name of the schema where the object or collection is defined.

## setNumber()

Sets a parameter to a `Number` value.

### Syntax

```
void setNumber(  
    unsigned int paramIndex,  
    const Number &val);
```

Parameter	Description
paramIndex	Parameter index; first parameter is 1, second is 2, and so on.
val	The parameter value.

## setObject()

Sets the value of a parameter using an object; use the `C++.lang` equivalent objects for integral values. The OCCI specification specifies a standard mapping from `C++ Object` types to SQL types. The given parameter `C++` object will be converted to the corresponding SQL type before being sent to the database.

### Syntax

```
void setObject(  
    unsigned int paramIndex,  
    PObject* val);
```

Parameter	Description
paramIndex	Parameter index; first parameter is 1, second is 2, and so on.
val	The object containing the input parameter value.
sqltyp	The SQL type name of the object to be set.

## setPrefetchMemorySize()

Sets the amount of memory that will be used internally by OCCI to store data fetched during each round trip to the server. A value of 0 means that the amount of data fetched during the round trip is constrained by the `FetchRowCount` parameter. If both parameters are nonzero, the smaller of the two is used.

### Syntax

```
void setPrefetchMemorySize(  
    unsigned int bytes);
```

Parameter	Description
bytes	Number of bytes used for storing data fetched during each server round trip.

## setPrefetchRowCount()

Sets the number of rows that will be fetched internally by OCCI during each round trip to the server. A value of 0 means that the amount of data fetched during the round trip is constrained by the `FetchMemorySize` parameter. If both parameters are nonzero, the smaller of the two is used. If both of these parameters are zero, row count internally defaults to 1 row and that is the value returned from the `getFetchRowCount()` method.

### Syntax

```
void setPrefetchRowCount(
    unsigned int rowCount);
```

Parameter	Description
<code>rowCount</code>	Number of rows to fetch for each round trip to the server.

## setRef()

Sets the value of a parameter to a reference. A `Ref<T>` instance will be implicitly converted to a `RefAny` object during this call.

Syntax	Description
<pre>void setRef(     unsigned int paramIndex,     const RefAny &amp;refAny);</pre>	Sets the value of a parameter to a reference.
<pre>void setRef(     unsigned int paramIndex,     const RefAny &amp;refAny,     const string &amp;typeName,     const string &amp;schName = "");</pre>	Sets the value of a parameter to a reference. If the <code>Statement</code> represents a callable PL/SQL method, pass the schema name and type name of the object represented by the <code>Ref</code> . Support for <code>string</code> .
<pre>void setRef(     unsigned int paramIndex,     const RefAny &amp;refAny,     const UString &amp;typeName,     const UString &amp;schName);</pre>	Sets the value of a parameter to a reference. If the <code>Statement</code> represents a callable PL/SQL method, pass the schema name and type name of the object represented by the <code>Ref</code> . Support for <code>UString</code> .

Parameter	Description
<code>paramIndex</code>	Parameter index; first parameter is 1, second is 2, and so on.
<code>refAny</code>	The reference.
<code>typeName</code>	The type of the object [optional].
<code>schName</code>	The schema where the object type is defined [optional].

## setRowid()

Sets a `Rowid` bytes array for a bind position.

**Syntax**

```
void setRowid(
    unsigned int paramIndex,
    const Bytes &val);
```

Parameter	Description
paramIndex	Parameter index; first parameter is 1, second is 2, and so on.
val	The parameter value.

**setSQL()**

A new SQL string can be associated with a `Statement` object by this call. Resources associated with the previous SQL statement are freed. In particular, a previously obtained result set is invalidated. If an empty sql string, "", was used when the `Statement` was created, a `setSQL` method with the proper SQL string must be done prior to execution.

**Syntax**

```
void setSQL(
    const string &sql);
```

Parameter	Description
sql	Any SQL statement.

**setSQLUString()**

Associate an SQL statement with this object. Unicode support: the client `Environment` should be initialized in `OCCIUTF16` mode.

**Syntax**

```
void setSQLUString(
    const UString &sql);
```

Parameter	Description
sql	A SQL statement in same character set as the connection source of the statement.

**setString()**

Sets a parameter for a specified index.

**Syntax**

```
void setString(
    unsigned int paramIndex,
    const string &val);
```

Parameter	Description
paramIndex	Parameter index; first parameter is 1, second is 2, and so on.

Parameter	Description
val	The parameter value.

## setTimestamp()

Sets a parameter to a Timestamp value.

### Syntax

```
void setTimestamp(
    unsigned int paramIndex,
    const Timestamp &val);
```

Parameter	Description
paramIndex	Parameter index; first parameter is 1, second is 2, and so on.
val	The parameter value.

## setUInt()

Sets a parameter to a C++ unsigned int value.

### Syntax

```
void setUInt(
    unsigned int paramIndex,
    unsigned int val);
```

Parameter	Description
paramIndex	Parameter index; first parameter is 1, second is 2, and so on.
val	The parameter value.

## setUString()

Sets a parameter for a specified index; globalization enabled.

### Syntax

```
void setUString(
    unsigned int paramIndex,
    const UString &val);
```

Parameter	Description
paramIndex	Parameter index; first parameter is 1, second is 2, and so on.
val	The parameter value.

## setVector()

Sets a parameter to a vector. This method should be used when the type is a collection type, varrays or nested tables. The SQL Type of the elements in the collection should be compatible with the type of the vector. For example, if the collection is a varray of VARCHAR2, use `vector<string>`.

Syntax	Description
<pre>void setVector(     Statement *stmt,     unsigned int paramIndex,     const vector&lt; T &gt; &amp;vect,     const string &amp;schemaName,     const string &amp;typeName);</pre>	Intended for use on platforms where partial ordering of function templates is not supported, such as Windows NT and z/OS. Multibyte support.
<pre>void setVector(     Statement *stmt,     unsigned int paramIndex,     const vector&lt;T* &gt; &amp;vect,     const string &amp;schemaName,     const string &amp;typeName);</pre>	Intended for use on platforms where partial ordering of function templates is supported. Multibyte support.
<pre>void setVector(     Statement *stmt,     unsigned int paramIndex,     const vector&lt;BDouble&gt; &amp;vect,     const string &amp;sqltype);</pre>	Sets a BDouble vector.
<pre>void setVector(     Statement *stmt,     unsigned int paramIndex,     const vector&lt;Bfile&gt; &amp;vect,     const string &amp;schemaName,     const string &amp;typeName);</pre>	Sets a const Bfile vector; multibyte support.
<pre>void setVector(     Statement *stmt,     unsigned int paramIndex,     const vector&lt;Bfile&gt; &amp;vect,     const UString &amp;schemaName,     const UString &amp;typeName);</pre>	Sets a const BFile vector; UTF16 support.
<pre>void setVector(     Statement *stmt,     unsigned int paramIndex,     const vector&lt;BFloat&gt; &amp;vect,     const string &amp;sqltype);</pre>	Sets a BFloat vector.
<pre>void setVector(     Statement *stmt,     unsigned int paramIndex,     const vector&lt;Blob&gt; &amp;vect,     const string &amp;schemaName,     const string &amp;typeName);</pre>	Sets a const Blob vector; multibyte support.
<pre>void setVector(     Statement *stmt,     unsigned int paramIndex,     const vector&lt;Blob&gt; &amp;vect,     const UString &amp;schemaName,     const UString &amp;typeName);</pre>	Sets a const Blob vector; UTF16 support.

Syntax	Description
<pre>void setVector(     Statement *stmt,     unsigned int paramIndex,     const vector&lt;Clob&gt; &amp;vect,     const string &amp;schemaName,     const string &amp;typeName);</pre>	Sets a const Clob vector; multibyte support.
<pre>void setVector(     Statement *stmt,     unsigned int paramIndex,     const vector&lt;Clob&gt; &amp;vect,     const UString &amp;schemaName,     const UString &amp;typeName);</pre>	Sets a const Clob vector; UTF16 support.
<pre>void setVector(     Statement *stmt,     unsigned int paramIndex,     const vector&lt;Date&gt; &amp;vect,     const string &amp;schemaName,     const string &amp;typeName);</pre>	Sets a const Date vector; multibyte support.
<pre>void setVector(     Statement *stmt,     unsigned int paramIndex,     const vector&lt;Date&gt; &amp;vect,     const UString &amp;schemaName,     const UString &amp;typeName);</pre>	Sets a const Date vector; UTF16 support.
<pre>void setVector(     Statement *stmt,     unsigned int paramIndex,     const vector&lt;double&gt; &amp;vect,     const string &amp;schemaName,     const string &amp;typeName);</pre>	Sets a const double vector; multibyte support.
<pre>void setVector(     Statement *stmt,     unsigned int paramIndex,     const vector&lt;double&gt; &amp;vect,     const UString &amp;schemaName,     const UString &amp;typeName);</pre>	Sets a const double vector; UTF16 support.
<pre>void setVector(     Statement *stmt,     unsigned int paramIndex,     const vector&lt;float&gt; &amp;vect,     const string &amp;schemaName,     const string &amp;typeName);</pre>	Sets a const float vector; multibyte support.
<pre>void setVector(     Statement *stmt,     unsigned int paramIndex,     const vector&lt;float&gt; &amp;vect,     const UString &amp;schemaName,     const UString &amp;typeName);</pre>	Sets a const float vector; UTF16 support.
<pre>void setVector(     Statement *stmt,     unsigned int paramIndex,     const vector&lt;int&gt; &amp;vect,     const string &amp;schemaName,     const string &amp;typeName);</pre>	Sets a const int vector; multibyte support.

Syntax	Description
<pre>void setVector(     Statement *stmt,     unsigned int paramIndex,     const vector&lt;int&gt; &amp;vect,     const UString &amp;schemaName,     const UString &amp;typeName);</pre>	Sets a const int vector; UTF16 support.
<pre>void setVector(     Statement *stmt,     unsigned int paramIndex,     const vector&lt;IntervalDS&gt; &amp;vect,     const string &amp;schemaName,     const string &amp;typeName);</pre>	Sets a const IntervalDS vector; multibyte support.
<pre>void setVector(     Statement *stmt,     unsigned int paramIndex,     const vector&lt;IntervalDS&gt; &amp;vect,     const UString &amp;schemaName,     const UString &amp;typeName);</pre>	Sets a const IntervalDS vector; UTF16 support.
<pre>void setVector(     Statement *stmt,     unsigned int paramIndex,     const vector&lt;IntervalYM&gt; &amp;vect,     const string &amp;schemaName,     const string &amp;typeName);</pre>	Sets a const IntervalYM vector; multibyte support.
<pre>void setVector(     Statement *stmt,     unsigned int paramIndex,     const vector&lt;IntervalYM&gt; &amp;vect,     const UString &amp;schemaName,     const UString &amp;typeName);</pre>	Sets a const IntervalYM vector; UTF16 support.
<pre>void setVector(     Statement *stmt,     unsigned int paramIndex,     const vector&lt;Number&gt; &amp;vect,     const string &amp;schemaName,     const string &amp;typeName);</pre>	Sets a const Number vector; multibyte support.
<pre>void setVector(     Statement *stmt,     unsigned int paramIndex,     const vector&lt;Number&gt; &amp;vect,     const UString &amp;schemaName,     const UString &amp;typeName);</pre>	Sets a const Number vector; UTF16 support.
<pre>void setVector(     Statement *stmt,     unsigned int paramIndex,     const vector&lt;RefAny&gt; &amp;vect,     const string &amp;schemaName,     const string &amp;typeName);</pre>	Sets a const RefAny vector; multibyte support.
<pre>void setVector(     Statement *stmt,     unsigned int paramIndex,     const vector&lt;RefAny&gt; &amp;vect,     const UString &amp;schemaName,     const UString &amp;typeName);</pre>	Sets a const RefAny vector; UTF16 support.



Syntax	Description
<pre>void setVector(     Statement *stmt,     unsigned int paramIndex,     const vector&lt;string&gt; &amp;vect,     const string &amp;schemaName,     const string &amp;typeName);</pre>	Sets a const string vector; multibyte support.
<pre>void setVector(     Statement *stmt,     unsigned int paramIndex,     const vector&lt;string&gt; &amp;vect,     const UString &amp;schemaName,     const UString &amp;typeName);</pre>	Sets a const string vector; UTF16 support.
<pre>void setVector(     Statement *stmt,     unsigned int paramIndex,     const vector&lt;Timestamp&gt; &amp;vect,     const string &amp;schemaName,     const string &amp;typeName);</pre>	Sets a const Timestamp vector; multibyte support.
<pre>void setVector(     Statement *stmt,     unsigned int paramIndex,     const vector&lt;Timestamp&gt; &amp;vect,     const UString &amp;schemaName,     const UString &amp;typeName);</pre>	Sets a const Timestamp vector; UTF16 support.
<pre>void setVector(     Statement *stmt,     unsigned int paramIndex,     const vector&lt;unsigned int&gt; &amp;vect,     const string &amp;schemaName,     const string &amp;typeName);</pre>	Sets a const unsigned int vector; multibyte support.
<pre>void setVector(     Statement *stmt,     unsigned int paramIndex,     const vector&lt;unsigned int&gt; &amp;vect,     const UString &amp;schemaName,     const UString &amp;typeName);</pre>	Sets a const unsigned int vector; UTF16 support.
<pre>void setVector(     Statement *stmt,     unsigned int paramIndex,     vector&lt;Bfile&gt; &amp;vect,     string &amp;sqltype);</pre>	Sets a Bfile vector.
<pre>void setVector(     Statement *stmt,     unsigned int paramIndex,     vector&lt;Blob&gt; &amp;vect,     string &amp;sqltype);</pre>	Sets a Blob vector.
<pre>void setVector(     Statement *stmt,     unsigned int paramIndex,     vector&lt;Clob&gt; &amp;vect,     string &amp;sqltype);</pre>	Sets a Clob vector.

<b>Syntax</b>	<b>Description</b>
<pre>void setVector(     Statement *stmt,     unsigned int paramIndex,     vector&lt;Date&gt; &amp;vect,     string &amp;sqltype);</pre>	Sets a Date vector.
<pre>void setVector(     Statement *stmt,     unsigned int paramIndex,     vector&lt;double&gt; &amp;vect,     string &amp;sqltype);</pre>	Sets a double vector.
<pre>void setVector(     Statement *stmt,     unsigned int paramIndex,     vector&lt;float&gt; &amp;vect,     string &amp;sqltype);</pre>	Sets a float vector.
<pre>void setVector(     Statement *stmt,     unsigned int paramIndex,     vector&lt;int&gt; &amp;vect,     string &amp;sqltype);</pre>	Sets an int vector.
<pre>void setVector(     Statement *stmt,     unsigned int paramIndex,     vector&lt;IntervalDS&gt; &amp;vect,     string &amp;sqltype);</pre>	Sets an IntervalDS vector.
<pre>void setVector(     Statement *stmt,     unsigned int paramIndex,     vector&lt;IntervalYM&gt; &amp;vect,     string &amp;sqltype);</pre>	Sets an IntervalYM vector.
<pre>void setVector(     Statement *stmt,     unsigned int paramIndex,     vector&lt;Number&gt; &amp;vect,     string &amp;sqltype);</pre>	Sets a Number vector.
<pre>void setVector(     Statement *stmt,     unsigned int paramIndex,     vector&lt;RefAny&gt; &amp;vect,     string &amp;sqltype);</pre>	Sets a RefAny vector.
<pre>void setVector(     Statement *stmt,     unsigned int paramIndex,     vector&lt;string&gt; &amp;vect,     string &amp;sqltype);</pre>	Sets a string vector.
<pre>void setVector(     Statement *stmt,     unsigned int paramIndex,     vector&lt;Timestamp&gt; &amp;vect,     string &amp;sqltype);</pre>	Sets a Timestamp vector.

Syntax	Description
<pre>void setVector(     Statement *stmt,     unsigned int paramIndex,     vector&lt;unsigned int&gt; &amp;vect,     string &amp;sqltype);</pre>	Sets an unsigned int vector.
<pre>template &lt;class T&gt; void setVector(     Statement *stmt,     unsigned int paramIndex,     const vector&lt; T* &gt; &amp;vect,     const string &amp;sqltype);</pre>	Intended for use on platforms where partial ordering of function templates is <i>not</i> supported.
<pre>template &lt;class T&gt; void setVector(     Statement *stmt,     unsigned int paramIndex,     const vector&lt;T&gt; &amp;vect,     const string &amp;sqltype);</pre>	Intended for use on platforms where partial ordering of function templates is supported.
<pre>template &lt;class T&gt; void setVector(     Statement *stmt,     unsigned int paramIndex,     vector&lt;Ref&lt;T&gt;&gt; &amp;vect,     string &amp;sqltype);</pre>	Available only on platforms where partial ordering of function templates is supported. <a href="#">setVectorOfRefs()</a> can be used instead.

Parameter	Description
stmt	Statement on which parameter is to be set.
paramIndex	Parameter index; first parameter is 1, second is 2, and so on.
vect	The vector to be set.
sqltype	Sqltype of the collection in the database. For example, CREATE TYPE num_coll AS VARRAY OF NUMBER. And the column/parameter type is num_coll. The sqltype would be num_coll.
schemaName	Name of the schema used
typeName	Type

## setVectorOfRefs()

Sets a parameter to a vector; should be used when the type is a collection of REFS or nested tables of REFS.

Syntax	Description
<pre>template &lt;class T&gt; void setVectorOfRefs(     Statement *stmt, unsigned int paramIndex,     const vector&lt;Ref&lt;T&gt; &gt; &amp;vect,     const string &amp;sqltype);</pre>	Sets a parameter to a vector; should be used when the type is a collection of REFS are varrays or nested tables of REFS.

Syntax	Description
<pre>template &lt;class T&gt; void setVectorOfRefs(     Statement *stmt,     unsigned int paramIndex,     const vector&lt;Ref&lt;T&gt; &gt; &amp;vect,     const string &amp;sqltype);</pre>	Used for multibyte support.
<pre>template &lt;class T&gt; void setVectorOfRefs(     Statement *stmt,     unsigned int paramIndex,     const vector&lt;Ref&lt;T&gt;&gt; &amp;vect,     const string &amp;schemaName,     const string &amp;typeName);</pre>	Used for multibyte support.
<pre>template &lt;class T&gt; void setVectorOfRefs(     Statement *stmt,     unsigned int paramIndex,     const vector&lt;Ref&lt;T&gt; &amp;vect,     const UString &amp;schemaName,     const UString &amp;typeName);</pre>	Used for UTF16 support on platforms where partial ordering of function templates is not supported, such as Windows NT and z/OS.
<pre>template &lt;class T&gt; void setVector(     Statement *stmt,     unsigned int paramIndex,     const vector&lt;T* &gt; &amp;vect,     const UString &amp;schemaName,     const UString &amp;typeName);</pre>	Used for UTF16 support on platforms where partial ordering of function templates is supported.

Parameter	Description
stmt	Statement on which parameter is to be set.
paramIndex	Parameter index; first parameter is 1, second is 2, and so on.
vect	Vector to be set.
sqltype	Sqltype of the parameter or column. Use <a href="#">setVectorOfRefs()</a> instead of specialized function <a href="#">setVector()</a> for Ref<T>.
schemaName	Name of the schema used
typeName	Type

## status()

Returns the current status of the statement. Useful when there is streamed data to be written (or read). Other methods such as [getCurrentStreamParam\(\)](#) and [getCurrentIteration\(\)](#) can be called to find out the streamed parameter that needs to be written and the current iteration number for an iterative or array execute. The [status\(\)](#) method can be called repeatedly to find out the status of the execution.

The returned value, Status, is defined in [Table 13-42](#) on page 13-212.

### Syntax

```
Status status() const;
```

## Stream Class

You use a `Stream` to read or write streamed data (usually `LONG`).

- A read-able `Stream` is used to obtain streamed data from a result set or `OUT` bind variable from a stored procedure call. A read-able `Stream` must be read completely until the end of data is reached or it should be closed to discard any unwanted data.
- A write-able `Stream` is used to provide streamed data (usually `LONG`) to parameterized statements including callable statements.

**Table 13–44 Enumerated Values Used by Stream Class**

Attribute	Options
Status	<ul style="list-style-type: none"> <li>■ <code>READY_FOR_READ</code> indicates that the <code>Stream</code> is ready for read operations</li> <li>■ <code>READY_FOR_WRITE</code> indicates that the <code>Stream</code> is ready for write operations</li> <li>■ <code>INACTIVE</code> indicates that the <code>Stream</code> is not available for ready or write operations</li> </ul>

**Table 13–45 Summary of Stream Methods**

Method	Summary
<a href="#">readBuffer()</a> on page 13-253	Reads the stream and returns the amount of data read from the <code>Stream</code> object.
<a href="#">readLastBuffer()</a> on page 13-254	Reads last buffer from <code>Stream</code> .
<a href="#">writeBuffer()</a> on page 13-254	Writes data from buffer to the stream.
<a href="#">writeLastBuffer()</a> on page 13-254	Writes the last data from buffer to the stream.
<a href="#">status()</a> on page 13-254	Returns the current status of the stream.

### readBuffer()

Reads data from `Stream`. The `size` parameter specifies the maximum number of byte characters to read. Returns the amount of data read from the `Stream` object. -1 means end of data on the stream.

#### Syntax

```
virtual int readBuffer(
    char *buffer,
    unsigned int size) = 0;
```

Parameter	Description
<code>buffer</code>	Pointer to data buffer; must be allocated and freed by caller.
<code>size</code>	Specifies the number of bytes to be read.

## readLastBuffer()

Reads the last buffer from the `Stream`. It can also be called to discard unread data. The size parameter specifies the maximum number of byte characters to read. Returns the amount of data read from the `Stream` object; -1 means end of data on the stream.

### Syntax

```
virtual int readLastBuffer(  
    char *buffer,  
    unsigned int size) = 0;
```

Parameter	Description
buffer	Pointer to data buffer; must be allocated and freed by caller.
size	Specifies the number of bytes to be read.

## writeBuffer()

Writes data from buffer to the stream. The amount of data is determined by `size`.

### Syntax

```
virtual void writeBuffer(  
    char *buffer,  
    unsigned int size) = 0;
```

Parameter	Description
buffer	Pointer to data buffer.
size	Specifies the number of chars to be written.

## writeLastBuffer()

This method writes the last data buffer to the stream. It can also be called to write the last chunk of data. The amount of data written is determined by `size`.

### Syntax

```
virtual void writeLastBuffer(  
    char *buffer,  
    unsigned int size) = 0;
```

Parameter	Description
buffer	Pointer to data buffer.
size	Specifies the number of bytes to be written.

## status()

Returns the current `Status`, as defined in [Table 13-44](#) on page 13-253.

**Syntax**

```
virtual Status status() const;
```

## Subscription Class

The subscription class encapsulates the information and operations necessary for registering a subscriber for notification.

**Table 13–46 Enumerated Values Used by Subscription Class**

Attribute	Options
Presentation	<ul style="list-style-type: none"> <li>■ PRES_DEFAULT indicates that the event notification should be in default format.</li> <li>■ PRES_XML indicates that the event notification should be in XML format.</li> </ul>
Protocol	<ul style="list-style-type: none"> <li>■ PROTO_CBK indicates that the client will receive notifications through the default system protocol.</li> <li>■ PROTO_MAIL indicates that the client will receive notifications through e-mail, like <code>xyz@oracle.com</code>. The database does not check if the e-mail is valid.</li> <li>■ PROTO_SERVER indicates that the client will receive notifications through an invoked PL/SQL procedure in the database, like <code>schema.procedure</code>. The subscriber must have the appropriate permissions on the procedure.</li> <li>■ PROTO_HTTP indicates that the client will receive notifications through an HTTP URL, like <code>http://www.oracle.com:80</code>. The database does not check if the URL is valid.</li> </ul>
Namespace	<ul style="list-style-type: none"> <li>■ NS_ANONYMOUS indicates that the registrations will be made in an anonymous namespace.</li> <li>■ NS_AQ indicates that the registrations will be made in the Oracle Streams Advanced Queuing namespace.</li> </ul>

**Table 13–47 Summary of Subscription Methods**

Method	Summary
<a href="#">Subscription()</a> on page 13-257	Subscription class constructor.
<a href="#">getCallbackContext()</a> on page 13-258	Retrieves the callback context.
<a href="#">getDatabaseServersCount()</a> on page 13-258	Retrieves the number of database servers in which the client is interested for the registration.
<a href="#">getDatabaseServerNames()</a> on page 13-258	Returns the names of all the database servers where the client registered an interest for notification.
<a href="#">getNotifyCallback()</a> on page 13-258	Returns the pointer to the registered callback function.
<a href="#">getPayload()</a> on page 13-258	Retrieves the payload that has been set on the Subscription object prior to posting.
<a href="#">getSubscriptionName()</a> on page 13-259	Retrieves the name of the Subscription.
<a href="#">getSubscriptionNamespace()</a> on page 13-259	Retrieves the namespace of the Subscription.
<a href="#">getRecipientName()</a> on page 13-259	Retrieves the name of the Subscription recipient.
<a href="#">getPresentation()</a> on page 13-259	Retrieves the notification presentation mode.



**Table 13-47 (Cont.) Summary of Subscription Methods**

Method	Summary
<a href="#">getProtocol()</a> on page 13-259	Retrieves the notification protocol.
<a href="#">isNull()</a> on page 13-259	Determines if the <code>Subscription</code> is <code>NULL</code> .
<a href="#">operator=()</a> on page 13-260	Assignment operator for <code>Subscription</code> .
<a href="#">setCallbackContext()</a> on page 13-260	Registers a callback function for OCI protocol.
<a href="#">setDatabaseServerNames()</a> on page 13-260	Specifies the database server distinguished names from which the client will receive notifications.
<a href="#">setNotifyCallback()</a> on page 13-260	Specifies the context passed to user callbacks
<a href="#">setNull()</a> on page 13-261	Specifies the <code>Subscription</code> object to <code>NULL</code> and frees the memory associated with the object.
<a href="#">setSubscriptionName()</a> on page 13-262	Specifies the name of the subscription.
<a href="#">setSubscriptionNamespace()</a> on page 13-262	Specifies the namespace in which the subscription is used.
<a href="#">setPayload()</a> on page 13-261	Specifies the buffer content of the notification.
<a href="#">setRecipientName()</a> on page 13-262	Specifies the name of the recipient of the notification.
<a href="#">setPresentation()</a> on page 13-261	Specifies the presentation mode in which the client will receive notifications.
<a href="#">setProtocol()</a> on page 13-261	Specifies the protocol in which the client will receive notifications.
<a href="#">setSubscriptionName()</a> on page 13-262	Specifies the name of the subscription.
<a href="#">setSubscriptionNamespace()</a> on page 13-262	Specifies the namespace where the subscription is used.
<a href="#">setRecipientName()</a> on page 13-262	Specifies the name of the recipient of the notification.

## Subscription()

Subscription class constructor.

Syntax	Description
<code>Subscription (const Environment *env );</code>	Creates a <code>Subscription</code> within a specified <code>Environment</code> .
<code>Subscription(const Subscription&amp; sub);</code>	Copy constructor.

### Syntax

```
Subscription(const Subscription& sub);
```

Parameter	Description
<code>env</code>	The <code>Environment</code> .

Parameter	Description
sub	The original Subscription.

## getCallbackContext()

Retrieves the callback context.

### Syntax

```
void* getCallbackContext() const;
```

## getDatabaseServersCount()

Returns the number of database servers in which the client is interested for the registration.

### Syntax

```
unsigned int getDatabaseServersCount() const;
```

## getDatabaseServerNames()

Returns the names of all the database servers where the client registered an interest for notification.

### Syntax

```
vector<string> getDatabaseServerNames() const;
```

## getNotifyCallback()

Returns the pointer to the callback function registered for this Subscription.

### Syntax

```
unsigned int (*getNotifyCallback() const)(  
    Subscription& sub,  
    NotifyResult *nr);
```

---

Parameter	Description
sub	The Subscription.
nr	The NotifyResult.

---

## getPayload()

Retrieves the payload that has been set on the Subscription object prior to posting.

### Syntax

```
Bytes getCPayload() const;
```

## getSubscriptionName()

Retrieves the name of the subscription.

### Syntax

```
string getSubscriptionName() const;
```

## getSubscriptionNamespace()

Retrieves the namespace of the subscription. The subscription name must be consistent with its namespace. Valid `Namespace` values are `NS_AQ` and `NS_ANONYMOUS`, as defined in [Table 13-46](#) on page 13-256.

### Syntax

```
Namespace getSubscriptionNamespace() const;
```

## getRecipientName()

Retrieves the name of the recipient of the notification. Possible return values are E-mail address, the HTTP url and the PL/SQL procedure, depending on the protocol.

### Syntax

```
string getRecipientName() const;
```

## getPresentation()

Retrieves the presentation mode in which the client receives notifications. Valid `Presentation` values are defined in [Table 13-46](#) on page 13-256.

### Syntax

```
Presentation getPresentation() const;
```

## getProtocol()

Retrieves the protocol in which the client receives notifications. Valid `Protocol` values are defined in [Table 13-46](#) on page 13-256.

### Syntax

```
Protocol getProtocol() const;
```

## isNull()

Returns `TRUE` if `Subscription` is `NULL` or `FALSE` otherwise.

### Syntax

```
bool isNull() const;
```

## operator=()

Assignment operator for Subscription.

### Syntax

```
void operator=(
    const Subscription& sub);
```

Parameter	Description
sub	The original Subscription.

## setCallbackContext()

Registers a notification callback function when the protocol is `PROTO_CBK`, as defined in [Table 13-46](#) on page 13-256. Context registration is also included in this call.

### Syntax

```
void setCallbackContext(
    void *ctx);
```

Parameter	Description
ctx	The context set.

## setDatabaseServerNames()

Specifies the list of database server distinguished names from which the client will receive notifications.

### Syntax

```
void setDatabaseServerNames(
    const vector<string>& dbsrv);
```

Parameter	Description
dbsrv	The list of database distinguished names

## setNotifyCallback()

Sets the context that the client wants to get passed to the user callback. If the protocol is set to `PROTO_CBK` or not specified, this attribute needs to be set before registering the subscription handle.

### Syntax

```
void setNotifyCallback(
    unsigned int (*callback)(
        Subscription& sub,
```

```
NotifyResult *nr));
```

Parameter	Description
callback	The user callback function.
sub	The Subscription object.
nr	The NotifyResult object.

## setNull()

Sets the Subscription object to NULL and frees the memory associated with the object.

### Syntax

```
void setNull();
```

## setPayload()

Sets the buffer content that corresponds to the payload to be posted to the Subscription.

### Syntax

```
void setPayload(
    const Bytes& payload);
```

Parameter	Description
payload	Content of the notification.

## setPresentation()

Sets the presentation mode in which the client will receive notifications.

### Syntax

```
void setPresentation(
    Presentation pres);
```

Parameter	Description
pres	Presentation mode, as defined in <a href="#">Table 13-46</a> on page 13-256.

## setProtocol()

Sets the Protocol in which the client will receive event notifications, as defined in [Table 13-46](#) on page 13-256.

### Syntax

```
void setProtocol(
    Protocol prot);
```

Parameter	Description
prot	Protocol mode

## setSubscriptionName()

Sets the name of the subscription. All subscriptions are identified by a subscription name, which consists of a sequence of bytes of specified length.

If the namespace is `NS_AQ`, the subscription name is:

- `SCHEMA.QUEUE` when registering on a single consumer queue
- `SCHEMA.QUEUE:CONSUMER_NAME` when registering on a multi-consumer queue

### Syntax

```
void setSubscriptionName(  
    const string& name);
```

Parameter	Description
name	Subscription name.

## setSubscriptionNamespace()

Sets the namespace where the subscription is used. The subscription name must be consistent with its namespace. Default value is `NS_AQ`.

### Syntax

```
void setSubscriptionNamespace(  
    Namespace nameSpace);
```

Parameter	Description
nameSpace	Namespace in which the subscription is used, as defined in <a href="#">Table 13-46</a> on page 13-256.

## setRecipientName()

Sets the name of the recipient of the notification.

### Syntax

```
void setRecipientName(  
    const string& name);
```

Parameter	Description
name	Name of the notification recipient.

## Timestamp Class

This class conforms to the SQL92 `TIMESTAMP` and `TIMESTAMPTZ` types, and works with all database `TIMESTAMP` types: `TIMESTAMP`, `TIMESTAMP WITH TIME ZONE`, and `TIMESTAMP WITH LOCAL TIME ZONE`.

`Timestamp` time components, such as hour, minute, second and fractional section are in the time zone specified for the `Timestamp`. This is new behavior for the 10g release; previous versions supported GMT values of time components. Time components were only converted to the time zone specified by `Timestamp` when they were stored in the database. For example, the following `Timestamp()` call constructs a `Timestamp` value 13-Nov 2003 17:24:30.0 in timezone +5:30.

```
Timestamp ts(env, 2003, 11, 13, 17, 24, 30, 0, 5, 30);
```

The behavior of this call in previous releases would interpret the timestamp components as GMT, resulting in a timestamp value of 13-Nov 2003 11:54:30.0 in timezone +5:30. Users were forced to convert the timestamps to GMT before invoking the constructor.

---



---

**Note:** For GMT timezone, both hour and minute equal 0.

---



---

This behavior change also applies to `setDate()` and `setTime()` methods.

The fields of `Timestamp` class and their legal ranges are provided in [Table 13-48](#). An `SQLException` will occur if a parameter is out of range.

**Table 13-48** *Fields of Timestamp and Their Legal Ranges*

Field	Type	Minimum Value	Maximum value
year	int	-4713	9999
month	unsigned int	1	12
day	unsigned int	1	31
hour	unsigned int	0	23
min	unsigned int	0	59
sec	unsigned int	0	61
tzhour	int	-12	14
tzmin	int	-59	59

**Table 13-49** *Summary of Timestamp Methods*

Method	Summary
<a href="#">Timestamp()</a> on page 13-264	<code>Timestamp</code> class constructor.
<a href="#">fromText()</a> on page 13-266	Sets the time stamp from the values provided by the string.
<a href="#">getDate()</a> on page 13-267	Gets the date from the <code>Timestamp</code> object.
<a href="#">getTime()</a> on page 13-267	Gets the time from the <code>Timestamp</code> object.
<a href="#">getTimeZoneOffset()</a> on page 13-268	Returns the time zone hour and minute offset value.

**Table 13–49 (Cont.) Summary of Timestamp Methods**

Method	Summary
<a href="#">intervalAdd()</a> on page 13-268	Returns a <code>Timestamp</code> object with value (this + interval).
<a href="#">intervalSub()</a> on page 13-268	Returns a <code>Timestamp</code> object with value (this - interval).
<a href="#">isNull()</a> on page 13-269	Checks if <code>Timestamp</code> is <code>NULL</code> .
<a href="#">operator=()</a> on page 13-269	Simple assignment.
<a href="#">operator==(())</a> on page 13-269	Checks if a and b are equal.
<a href="#">operator!=(())</a> on page 13-269	Checks if a and b are not equal.
<a href="#">operator&gt;()</a> on page 13-270	Checks if a is greater than b.
<a href="#">operator&gt;=()</a> on page 13-270	Checks if a is greater than or equal to b.
<a href="#">operator&lt;()</a> on page 13-270	Checks if a is less than b.
<a href="#">operator&lt;=()</a> on page 13-271	Checks if a is less than or equal to b.
<a href="#">setDate()</a> on page 13-271	Sets the year, month, day components contained for this timestamp.
<a href="#">setNull()</a> on page 13-271	Sets the value of <code>Timestamp</code> to <code>NULL</code>
<a href="#">setTime()</a> on page 13-271	Sets the day, hour, minute, second and fractional second components for this timestamp.
<a href="#">setTimeZoneOffset()</a> on page 13-272	Sets the hour and minute offset for time zone.
<a href="#">subDS()</a> on page 13-272	Returns a <code>IntervalDS</code> representing this - val.
<a href="#">subYM()</a> on page 13-272	Returns a <code>IntervalYM</code> representing this - val.
<a href="#">toText()</a> on page 13-273	Returns a <code>string</code> representation for the timestamp in the format specified.

## Timestamp()

`Timestamp` class constructor.

Syntax	Description
<pre>Timestamp(     const Environment *env,     int year=1,     unsigned int month=1,     unsigned int day=1,     unsigned int hour=0,     unsigned int min=0,     unsigned int sec=0,     unsigned int fs=0,     int tzhour=0,     int tzmin=0);  Timestamp();</pre>	<p>Returns a default <code>Timestamp</code> object. Time components are understood to be in the specified time zone.</p> <p>Returns a <code>NULL</code> <code>Timestamp</code> object. A <code>NULL</code> timestamp can be initialized by assignment or calling the <code>fromText()</code> method. Methods that can be called on <code>NULL</code> timestamp objects are <code>setNull()</code>, <code>isNull()</code> and <code>operator=()</code>.</p>



Syntax	Description
<pre>Timestamp(     const Environment *env,     int year,     unsigned int month,     unsigned int day,     unsigned int hour,     unsigned int min,     unsigned int sec,     unsigned int fs,     const string &amp;timezone);</pre>	<p>Multibyte support. The timezone can be passed as region, "US/Eastern", or as an offset from GMT, "+05:30". If an empty string is passed, then the time is considered to be in the current session's time zone. Used for constructing values for <code>TIMESTAMP WITH LOCAL TIME ZONE</code> types.</p>
<pre>Timestamp(     const Environment *env,     int year,     unsigned int month,     unsigned int day,     unsigned int hour,     unsigned int min,     unsigned int sec,     unsigned int fs,     const UString &amp;timezone);</pre>	<p>UTF16 (UString) support. The timezone can be passed as region, "US/Eastern", or as an offset from GMT, "+05:30". If an empty string is passed, then the time is considered to be in the current session's time zone. Used for constructing values for <code>TIMESTAMP WITH LOCAL TIME ZONE</code> types.</p>
<pre>Timestamp(     const Timestamp &amp;src);</pre>	<p>Copy constructor.</p>

Parameter	Description
year	Year component.
month	Month component.
day	Day component.
hour	Hour component.
minute	Minute component.
second	Second component.
fs	Fractional second component.
tzhour	Time zone difference hour component.
tzmin	Timezone difference minute component.
src	The original Timezone.

### **Example 13–11 Using Default Timestamp Constructor**

This example demonstrates that the default constructor creates a NULL value, and how you can assign a non-NULL value to a `Timestamp` and perform operations on it:

```
Environment *env = Environment::createEnvironment();

//create a null timestamp
Timestamp ts;
if(ts.isNull())
    cout << "\n ts is Null";

//assign a non null value to ts
Timestamp notNullTs(env, 2000, 8, 17, 12, 0, 0, 0, 5, 30);
```

```

ts = notNullTs;

//now all operations are valid on ts
int yr;
unsigned int mth, day;
ts.getDate(yr, mth, day);

```

### **Example 13–12 Using fromText() method to Initialize a NULL Timestamp Instance**

The following code example demonstrates how to use the `fromText()` method to initialize a NULL timestamp:

```

Environment *env = Environment::createEnvironment();

Timestamp ts1;
ts1.fromText("01:16:17.12 04/03/1825", "hh:mi:ssxff dd/mm/yyyy", "", env);

```

### **Example 13–13 Comparing Timestamps Stored in the Database**

The following code example demonstrates how to get the timestamp column from a result set, check whether the timestamp is NULL, get the timestamp value in string format, and determine the difference between 2 timestamps:

```

Timestamp reft(env, 2001, 1, 1);
ResultSet *rs=stmt->executeQuery(
    "select order_date from orders where customer_id=1");
rs->next();

//retrieve the timestamp column from result set
Timestamp ts=rs->getTimestamp(1);

//check timestamp for null
if(!ts.isNull())
{
    string tsstr=ts.toText(           //get the timestamp value in string format
        "dd/mm/yyyy hh:mi:ss [tzh:tzm]",0);
    if(reft<ts                       //compare timestamps
        IntervalDS ds=reft.subDS(ts); //get difference between timestamps
    }
}

```

## **fromText()**

Sets the timestamp value from the string. The string is expected to be in the format specified. If `nlsParam` is specified, this will determine the NLS parameters to be used for the conversion. If `nlsParam` is not specified, the NLS parameters are picked up from the environment which has been passed. In case environment is not passed, Globalization Support parameters are obtained from the environment associated with the instance, if any.

Sets `Timestamp` object to value represented by a `string` or `UString`.

The value is interpreted based on the `fmt` and `nlsParam` parameters. In cases where `nlsParam` is not passed, the Globalization Support settings of the `envp` parameter are used.

**See Also:** *Oracle Database SQL Language Reference* for information on `TO_DATE`

Syntax	Description
<pre>void fromText(     const string &amp;timestampStr,     const string &amp;fmt,     const string &amp;nlsParam = "",     const Environment *env = NULL);</pre>	Sets Timestamp object to value represented by a string.
<pre>void fromText(     const UString &amp;timestampStr,     const UString &amp;fmt,     const UString &amp;nlsParam,     const Environment *env = NULL);</pre>	Sets Timestamp object to value represented by a UString; globalization enabled.

Parameter	Description
timestampStr	The timestamp string or UString to be converted to a Timestamp object.
fmt	The format string.
nlsParam	The NLS parameters string. If nlsParam is specified, this determines the NLS parameters to be used for the conversion. If nlsParam is not specified, the NLS parameters are picked up from envp.
env	The OCCI environment. In globalization enabled version of the method, used to determine NLS_CALENDAR for interpreting timestampStr. If env is not passed, the environment associated with the object controls the setting. Should be a non-NULL value if called on a NULL Timestamp object.

## getDate()

Returns the year, month and day values of the Timestamp.

### Syntax

```
void getDate(
    int &year,
    unsigned int &month,
    unsigned int &day) const;
```

Parameter	Description
year	Year component.
month	Month component.
day	Day component.

## getTime()

Returns the hour, minute, second, and fractional second components

### Syntax

```
void getTime(
    unsigned int &hour,
    unsigned int &minute,
    unsigned int &second,
    unsigned int &fs) const;
```

Parameter	Description
hour	Hour component.
minute	Minute component.
second	Second component.
fs	Fractional second component.

## getTimeZoneOffset()

Returns the time zone offset in hours and minutes.

### Syntax

```
void getTimeZoneOffset(  
    int &hour,  
    int &minute) const;
```

Parameter	Description
hour	Time zone hour.
minute	Time zone minute.

## intervalAdd()

Adds an interval to timestamp.

Syntax	Description
<pre>const Timestamp intervalAdd(     const IntervalDS&amp; val) const;</pre>	Adds an IntervalDS interval to the timestamp.
<pre>const Timestamp intervalAdd(     const IntervalYM&amp; val) const;</pre>	Adds an IntervalYM interval to the timestamp.

Parameter	Description
val	Interval to be added.

## intervalSub()

Subtracts an interval from a timestamp and returns the result as a timestamp. Returns a Timestamp with the value of this - val.

Syntax	Description
<pre>const Timestamp intervalSub(     const IntervalDS&amp; val) const;</pre>	Subtracts an IntervalDS interval to the timestamp.
<pre>const Timestamp intervalSub(     const IntervalYM&amp; val) const;</pre>	Subtracts an IntervalYM interval to the timestamp.

Parameter	Description
val	Interval to be subtracted.

## isNull()

Returns TRUE if Timestamp is NULL or FALSE otherwise.

### Syntax

```
bool isNull() const;
```

## operator=()

Assigns a given timestamp object to this object.

### Syntax

```
Timestamp & operator=(  
    const Timestamp &src);
```

Parameter	Description
src	Value to be assigned.

## operator==(())

Compares the timestamps specified. If the timestamps are equal, returns TRUE, FALSE otherwise. If either a or b is NULL then FALSE is returned.

### Syntax

```
bool operator==(  
    const Timestamp &first,  
    const Timestamp &second);
```

Parameter	Description
first	First timestamp to be compared.
second	Second timestamp to be compared.

## operator!=(())

Compares the timestamps specified. If the timestamps are not equal then TRUE is returned; otherwise, FALSE is returned. If either timestamp is NULL then FALSE is returned.

### Syntax

```
bool operator!=(  
    const Timestamp &first,  
    const Timestamp &second);
```

Parameter	Description
first	First timestamp to be compared.
second	Second timestamp to be compared.

**operator>()**

Returns `TRUE` if `first` is greater than `second`, `FALSE` otherwise. If either is `NULL` then `FALSE` is returned.

**Syntax**

```
bool operator>(
    const Timestamp &first,
    const Timestamp &second);
```

Parameter	Description
first	First timestamp to be compared.
second	Second timestamp to be compared.

**operator>=()**

Compares the timestamps specified. If the `first` timestamp is greater than or equal to the `second` timestamp then `TRUE` is returned; otherwise, `FALSE` is returned. If either timestamp is `NULL` then `FALSE` is returned.

**Syntax**

```
bool operator>=(
    const Timestamp &first,
    const Timestamp &second);
```

Parameter	Description
first	First timestamp to be compared.
second	Second timestamp to be compared.

**operator<()**

Returns `TRUE` if `first` is less than `second`, `FALSE` otherwise. If either `a` or `b` is `NULL` then `FALSE` is returned.

**Syntax**

```
bool operator<(
    const Timestamp &first,
    const Timestamp &second);
```

Parameter	Description
first	First timestamp to be compared.

Parameter	Description
second	Second timestamp to be compared.

## operator<=()

Compares the timestamps specified. If the first timestamp is less than or equal to the second timestamp then `TRUE` is returned; otherwise, `FALSE` is returned. If either timestamp is `NULL` then `FALSE` is returned.

### Syntax

```
bool operator<=(
    const Timestamp &first,
    const Timestamp &second);
```

Parameter	Description
first	First timestamp to be compared.
second	Second timestamp to be compared.

## setDate()

Sets the year, month, day components contained for this timestamp

### Syntax

```
void setDate(
    int year,
    unsigned int month,
    unsigned int day);
```

Parameter	Description
year	Year component. Valid values are -4713 through 9999.
month	Month component. Valid values are 1 through 12.
day	Day component. Valid values are 1 through 31.

## setNull()

Sets the timestamp to `NULL`.

### Syntax

```
void setNull();
```

## setTime()

Sets the day, hour, minute, second and fractional second components for this timestamp.

### Syntax

```
void setTime(
```

## setTimeZoneOffset()

---

```
unsigned int hour,  
unsigned int minute,  
unsigned int second,  
unsigned int fs);
```

Parameter	Description
hour	Hour component. Valid values are 0 through 23.
minute	Minute component. Valid values are 0 through 59.
second	Second component. Valid values are 0 through 59.
fs	Fractional second component.

## setTimeZoneOffset()

Sets the hour and minute offset for time zone.

### Syntax

```
void setTimeZoneOffset(  
    int hour,  
    int minute);
```

Parameter	Description
hour	Time zone hour. Valid values are -12 through 12.
minute	Time zone minute. Valid values are -59 through 59.

## subDS()

Computes the difference between this timestamp and the specified timestamp and return the difference as an `IntervalDS`.

### Syntax

```
const IntervalDS subDS(  
    const Timestamp& val) const;
```

Parameter	Description
val	Timestamp to be subtracted.

## subYM()

Computes the difference between timestamp values and return the difference as an `IntervalYM`.

### Syntax

```
const IntervalYM subYM(  
    const Timestamp& val) const;
```



Parameter	Description
val	Timestamp to be subtracted.

## toText()

Returns a `string` or `UString` representation for the timestamp in the format specified.

If `nlsParam` is specified, this will determine the NLS parameters to be used for the conversion. If `nlsParam` is not specified, the NLS parameters are picked up from the environment associated with the instance, if any.

**See Also:** *Oracle Database SQL Language Reference* for information on `TO_DATE`

Syntax	Description
<pre>string toText(     const string &amp;fmt,     unsigned int fspec,     const string &amp;nlsParam = "") const;</pre>	Returns a <code>string</code> representation for the timestamp in the format specified.
<pre>UString toText(     const UString &amp;fmt,     unsigned int fspec,     const UString &amp;nlsParam) const;</pre>	Returns a <code>UString</code> representation for the timestamp in the format specified; globalization enabled.

Parameter	Description
fmt	The format string.
fspec	The precision for the fractional second component of <code>Timestamp</code> .
nlsParam	The NLS parameters string. If <code>nlsParam</code> is specified, this determines the NLS parameters to be used for the conversion. If <code>nlsParam</code> is not specified, the NLS parameters are picked up from <code>envp</code> .

toText()

---

## A

---

ADR, 12-9  
  ADRC utility, 9-1, 12-11  
  base location, 12-9  
ADRCI, 12-11  
Agent class, 13-7  
  methods, 13-7  
AnyData class, 13-10  
  methods, 13-12  
  supported data types, 13-11  
  usage examples, 13-10  
application managed data buffering, 12-5  
application-provided serialization, 12-5  
associative access  
  overview, 4-9  
atomic null, 4-17  
attributes, 1-7  
automatic diagnostic repository (ADR), 12-9  
automatic serialization, 12-4

## B

---

BatchSQLException  
  methods, 13-19  
BatchSQLException class, 13-19  
Bfile class, 13-20  
  methods, 13-20  
BFILEs  
  external data type, 5-6  
bind operations  
  in bind operations, 1-7  
  out bind operations, 1-7  
Blob class, 13-26  
  methods, 13-26  
BLOBs  
  external data type, 5-7  
Bytes class, 13-34  
  methods, 13-34

## C

---

callable statements, 3-14  
  with arrays as parameters, 3-14  
CASE OTT parameter, 8-5  
CHAR

  external data type, 5-7  
classes  
  Agent class, 13-7  
  AnyData class, 13-10  
  BatchSQLException class, 13-19  
  Bfile class, 13-20  
  Blob class, 13-26  
  Bytes class, 13-34  
  Clob class, 13-37  
  Connection class, 13-48  
  ConnectionPool class, 13-62  
  Consumer class, 13-67  
  Date class, 13-75  
  Environment class, 13-85  
  IntervalDS class, 13-97  
  IntervalYM class, 13-107  
  Listener class, 13-116  
  Map class, 13-118  
  Message class, 13-119  
  Metadata class, 13-127  
  NotifyResult class, 13-141  
  Number class, 13-142  
  PObject class, 13-161  
  Producer class, 13-167  
  Ref class, 13-172  
  RefAny class, 13-177  
  ResultSet class, 3-19, 13-180  
  SQLException class, 13-199  
  StatelessConnectionPool class, 13-202  
  Statement class, 13-212  
  Stream class, 13-253  
  Subscription class, 13-256  
  Timestamp class, 13-263  
Clob class, 13-37  
  methods, 13-38  
CLOBs  
  external data type, 5-7  
CODE OTT parameter, 8-6  
collections  
  working with, 4-16  
committing a transaction, 3-23  
complex object retrieval  
  complex object, 4-14  
  depth level, 4-14  
  implementing, 4-14  
  overview, 4-14

- prefetch limit, 4-14
- root object, 4-14
- complex objects, 4-14
  - prefetching, 4-16
  - retrieving, 4-14
- CONFIG OTT parameter, 8-6
- configuration files
  - and the OTT utility, 8-2
- connecting to a database, 3-1
- Connection class, 13-48
  - methods, 13-48
- connection pool
  - createConnectionPool method, 3-3
  - creating, 3-3
- connection pooling, 3-3
  - transparent application failover, 12-3
- ConnectionPool class, 13-62
  - methods, 13-62
- Consumer class, 13-67
  - methods, 13-67
- control statements, 1-5

## D

---

- data buffering, 12-5
- data conversions
  - Date, 5-18
  - DATE data type, 5-17
  - internal data types, 5-16
  - Interval, 5-18
  - INTERVAL data types, 5-17
  - LOB data type, 5-17
  - LOBs, 5-17
  - Timestamp, 5-18
  - TIMESTAMP data types, 5-17
- data types, 5-1
  - AnyData, 13-11
  - OTT mappings, 8-18
  - overview, 5-1
  - types
    - external data types, 5-1, 5-4
    - internal data types, 5-1, 5-2
- Database, 3-8
- database
  - connecting to, 3-1
- database resident connection pooling, 3-8
  - administration, 3-9
  - using, 3-10
- DATE
  - external data type, 5-7
    - data conversion, 5-17
- Date class, 13-75
  - methods, 13-75
  - usage examples, 13-75
- DDL statements
  - executing, 3-11
- depth level, 4-14
- DML statements
  - executing, 3-11

## E

---

- elements, 1-3
- embedded objects, 4-2
  - creating, 4-3
  - fetching, 4-17
  - prefetching, 4-17
- Environment class, 13-85
  - methods, 13-85
- ERRTYPE OTT parameter, 8-6
- examples
  - Date class, 13-75
  - IntervalDS class, 13-97
  - IntervalYM class, 13-107
  - Number class, 13-142
- exception handling, 3-26
- executing SQL queries, 3-19
- executing statements dynamically, 3-21
- external data types, 5-6
  - BFILE, 5-6
  - BLOB, 5-7
  - CHAR, 5-7
  - CHARZ, 5-7
  - CLOB, 5-7
  - DATE, 5-7
  - FLOAT, 5-9
  - INTEGER, 5-9
  - INTERVAL DAY TO SECOND, 5-9
  - INTERVAL YEAR TO MONTH, 5-10
  - LONG, 5-10
  - LONG RAW, 5-10
  - LONG VARCHAR, 5-11
  - LONG VARRAW, 5-11
  - NCLOB, 5-11
  - NUMBER, 5-11
  - OCCI BFILE, 5-12
  - OCCI BLOB, 5-12
  - OCCI BYTES, 5-12
  - OCCI CLOB, 5-12
  - OCCI DATE, 5-12
  - OCCI INTERVALDS, 5-12
  - OCCI INTERVALYM, 5-12
  - OCCI NUMBER, 5-12
  - OCCI POBJECT, 5-12
  - OCCI REF, 5-12
  - OCCI REFANY, 5-12
  - OCCI STRING, 5-12
  - OCCI TIMESTAMP, 5-13
  - OCCI VECTOR, 5-13
  - RAW, 5-13
  - REF, 5-13
  - ROWID, 5-13
  - STRING, 5-13
  - TIMESTAMP, 5-13
  - TIMESTAMP WITH LOCAL TIME ZONE, 5-14
  - TIMESTAMP WITH TIME ZONE, 5-14
  - UNSIGNED INT, 5-14
  - VARCHAR, 5-14
  - VARCHAR2, 5-14
  - VARNUM, 5-15
  - VARRAW, 5-15

## F

---

fault diagnosability, 12-9

fields

IntervalDS class, 13-97

IntervalYM class, 13-107

Timestamp fields, 13-263

FLOAT

external data type, 5-9

## H

---

HFILE OTT parameter, 8-7

## I

---

Instant Client, 2-2

benefits, 2-2

connection names, 2-5

database connection, 2-5

environment variables, 2-5

Solaris, 2-6

Windows, 2-6

installation, 2-2

libraries, 2-4

Data Shared Library, 2-4

patching, 2-4

regenerating, 2-4

patching libraries, 2-4

SDK, 2-3

using, 2-4

Instant Client Light (English), 2-6

character sets, 2-6

errors, 2-6

globalization settings, 2-6

installation, 2-7

Client Admin Install, 2-7

Oracle Universal Installer, 2-7

OTN download, 2-7

using, 2-7

INTEGER

external data type, 5-9

internal data types, 5-2

CHAR, 5-3

LONG, 5-3

LONG RAW, 5-3

RAW, 5-3

VARCHAR2, 5-3

INTERVAL DAY TO SECOND

external data type, 5-9

INTERVAL YEAR TO MONTH

external data type, 5-10

IntervalDS class, 13-97

fields, 13-97

methods, 13-98

usage examples, 13-97

IntervalYM class, 13-107

fields, 13-107

methods, 13-108

usage examples, 13-107

INTYPE file

structure of, 8-14

INTYPE OTT parameter, 8-7

## L

---

Listener class, 13-116

methods, 13-116

LOBs

external data type

data conversion, 5-17

LONG

external data type, 5-10

LONG RAW

external data type, 5-10

LONG VARCHAR

external data type, 5-11

## M

---

manipulating object attributes, 4-12

Map class, 13-118

methods, 13-118

Message class, 13-119

methods, 13-119

metadata

argument and result attributes, 6-12

attributes, 6-5

code example, 6-2

collection attributes, 6-10

column attributes, 6-11

database attributes, 6-14

describing database objects, 6-2

list attributes, 6-13

overview, 6-1

package attributes, 6-7

parameter attributes, 6-5

procedure, function, and subprogram  
attributes, 6-7

schema attributes, 6-14

sequence attributes, 6-11

synonym attributes, 6-11

table and view attributes, 6-6

type attribute attributes, 6-9

type attributes, 6-7

type methods attributes, 6-9

MetaData class, 13-127

methods, 13-135

methods, 1-7

Agent methods, 13-7

AnyData methods, 13-12

BatchSQLException methods, 13-19

Bfile methods, 13-20

Blob methods, 13-26

Bytes methods, 13-34

Clob methods, 13-37

Connection methods, 13-48

ConnectionPool methods, 13-62

Consumer methods, 13-67

createConnection method, 3-2

createConnectionPool method, 3-3

- createEnvironment method, 3-2
- createProxyConnection method, 3-4
- createStatement method, 3-11
- Date methods, 13-75
- Environment class, 13-85
- execute method, 3-12
- executeArrayUpdate method, 3-12, 12-7
- executeQuery method, 3-12
- IntervalDS methods, 13-98
- IntervalYM class, 13-108
- Listener methods, 13-116
- Map methods, 13-118
- Message methods, 13-119
- MetaData class, 13-135
- NotifyResult methods, 13-141
- Number class, 13-143
- PObject methods, 13-161
- Producer methods, 13-167
- Ref methods, 13-172
- RefAny methods, 13-177
- ResultSet methods, 13-180
- setDataBuffer method, 12-6
- SQLException methods, 13-199
- StatelessConnectionPool, 13-202
- Statement, 13-212
- Stream methods, 13-253
- Subscription methods, 13-256
- terminateConnection method, 3-2, 3-3
- terminateEnvironment method, 3-3
- terminateStatement method, 3-13
- Timestamp methods, 13-263
- modifying rows iteratively, 12-8

## N

---

- navigational access
  - overview, 4-10
- NCLOBs
  - external data type, 5-11
- NEEDS\_STREAM\_DATA status, 3-21, 3-22
- nonprocedural elements, 1-3
- nonreferenceable objects, 4-2
- NotifyResult class, 13-141
  - methods, 13-141
- nullness, 4-17
- NUMBER
  - external data type, 5-11
- Number class, 13-142
  - methods, 13-143
  - usage examples, 13-142

## O

---

- object cache, 4-7, 4-8
  - flushing, 4-8
- object mode, 4-7
- object programming
  - overview, 4-1
  - using OCCI, 4-1
- object references

- using, 4-18
  - see also* REF
- Object Type Translator utility
  - see* OTT utility
- object types, 1-7
- objects
  - access using SQL, 4-10
  - attributes, 1-7
  - client-side, 1-8
  - dirty, 4-12
  - environment, 1-8
  - flushing, 4-12
  - freeing, 4-18
  - in OCCI, 4-2
  - inserting, 4-10
  - interfaces, 1-8
    - associative, 1-8
    - navigational, 1-8
  - manipulating attributes, 4-12
  - marking, 4-12
  - Metadata Class, 1-9
  - methods, 1-7
  - modifying, 4-10
  - object cache, 1-8
  - object types, 1-7
  - pinned, 4-11
  - pinning, 4-8, 4-11
  - recording database changes, 4-12
  - runtime environment, 1-8
  - transparent application failover, 12-2
- OCCI
  - benefits, 1-2
  - building applications, 1-2
  - functionality, 1-3
  - object mode, 4-7
  - overview, 1-1
  - special SQL terms, 1-6
- OCCI classes
  - Agent class, 13-7
  - AnyData class, 13-10
  - BatchSQLException class, 13-19
  - Bfile class, 13-20
  - Blob class, 13-26
  - Bytes class, 13-34
  - Clob class, 13-37
  - Connection class, 13-48
  - ConnectionPool class, 13-62
  - Consumer class, 13-67
  - Data class, 13-75
  - Environment class, 13-85
  - IntervalDS class, 13-97
  - IntervalYM class, 13-107
  - Listener class, 13-116
  - Map class, 13-118
  - Message class, 13-119
  - MetaData class, 13-127
  - NotifyResult class, 13-141
  - Number class, 13-142
  - PObject class, 13-161
  - Producer class, 13-167

- Ref class, 13-172
- RefAny class, 13-177
- ResultSet class, 13-180
- SQLException class, 13-199
- StatelessConnectionPool class, 13-202
- Statement class, 13-212
- Stream class, 13-253
- Subscription class, 13-256
- Timestamp class, 13-263
- OCCI environment
  - connection pool, 3-3
  - creating, 3-1
  - opening a connection, 3-2
  - scope, 3-2
  - terminating, 3-1
- OCCI program
  - example of, 4-21
- OCCI program development, 4-5
  - operational flow, 4-6
  - program structure, 4-5
- OCCI types
  - data conversion, 5-1
- optimizing performance, 3-20
  - setting prefetch count, 3-20
- OTT parameter TRANSITIVE, 8-9
- OTT parameters
  - CASE, 8-5
  - CODE, 8-6
  - CONFIG, 8-6
  - ERRTYPE, 8-6
  - HFILE, 8-7
  - INTYPE, 8-7
  - OUTTYPE, 8-8
  - SCHEMA\_NAMES, 8-8
  - USERID, 8-11
  - where they appear, 8-12
- OTT utility
  - benefits, 1-9
  - creating types in the database, 8-2
  - default name mapping, 8-22
  - description, 1-9
  - parameters, 8-4
  - using, 8-2
- out bind variables, 1-6
- OUTTYPE OTT parameter, 8-8

## P

---

- parameterized statements, 3-13
- performance
  - optimizing
    - executeArrayUpdate method, 12-7
    - setDataBuffer method, 12-6
- performance tuning
  - application managed data buffering, 12-5
  - array fetch using next() method, 12-8
  - data buffering, 12-5
- performance tuning, 12-1
  - connection sharing, 12-3
  - reading and writing multiple LOBs, 7-7

- shared server environments, 12-3
  - thread safety, 12-3
- thread safety, 12-3
- transparent application failover, 12-1
- persistent objects, 4-2
  - creating, 4-4
  - standalone objects, 4-3
  - types
    - embedded objects, 4-2
    - nonreferenceable objects, 4-2
    - referenceable objects, 4-2
    - standalone objects, 4-2
- pinning objects, 4-8, 4-11
- PL/SQL
  - out bind variables, 1-6
  - overview, 1-6
- PObject class, 13-161
  - methods, 13-161
- prefetch count
  - set, 3-20
- prefetch limit, 4-14
- PREPARED status, 3-21, 3-22
- procedural elements, 1-3
- Producer class, 13-167
  - methods, 13-167
- proxy connections, 3-4
  - using createProxyConnection method, 3-4

## Q

---

- queries, 1-5
  - how to specify, 3-20

## R

---

- RAW
  - external data type, 5-13
- REF
  - external data type, 5-13
  - retrieving a reference to an object
- Ref class, 13-172
  - methods, 13-172
- RefAny class, 13-177
  - methods, 13-177
- referenceable objects, 4-2
- relational programming
  - using OCCI, 3-1
- RESULT\_SET\_AVAILABLE status, 3-21, 3-22
- ResultSet class, 3-19, 13-180
  - methods, 13-180
- root object, 4-14
- ROWID
  - external data type, 5-13
- rows
  - iterative modification, 12-8
  - modify, 12-8

## S

---

- SCHEMA\_NAMES OTT parameter, 8-8
- shared connections

- using, 12-3
- shared server environments
  - application-provided serialization, 12-5
  - automatic serialization, 12-4
  - concurrency, 12-5
  - thread safety, 12-3
    - implementing, 12-4
- SQL statements
  - control statements, 1-5
  - DML statements, 1-5
  - processing of, 1-4
  - queries, 1-5
  - types
    - callable statements, 3-13, 3-14
    - parameterized statements, 3-13
    - standard statements, 3-13
- SQLException class, 13-199
  - methods, 13-199
- sqlnet.ora, 12-13
- standalone objects, 4-2
  - creating, 4-3
- standard statements, 3-13
- StatelessConnectionPool class, 13-202
  - methods, 13-202
- statement caching, 3-23
- Statement class, 13-212
  - methods, 13-212
- statement handles
  - creating, 3-11, 3-12
  - reusing, 3-12
  - terminating, 3-13
- status
  - NEEDS\_STREAM\_DATA, 3-21, 3-22
  - PREPARED, 3-21, 3-22
  - RESULT\_SET\_AVAILABLE, 3-21, 3-22
  - STREAM\_DATA\_AVAILABLE, 3-21, 3-23
  - UNPREPARED, 3-21
  - UPDATE\_COUNT\_AVAILABLE, 3-21, 3-22
- Stream class, 13-253
  - methods, 13-253
- STREAM\_DATA\_AVAILABLE status, 3-21, 3-23
- streamed reads, 3-15
- streamed writes, 3-15
- STRING
  - external data type, 5-13
- Subscription class, 13-256
  - methods, 13-256
- substitutability, 4-19

## T

---

- thread safety, 12-3
  - implementing, 12-4
- TIMESTAMP
  - external data type, 5-13
- Timestamp class
  - methods, 13-263
- TIMESTAMP WITH LOCAL TIME ZONE
  - external data type, 5-14
- TIMESTAMP WITH TIME ZONE

- external data type, 5-14
- transient objects, 4-2, 4-3
  - creating, 4-4, 4-5
- TRANSITIVE OTT parameter, 8-9
- transparent application failover, 12-1
  - connection pooling, 12-3
  - objects, 12-2
  - using, 12-2
- type inheritance, 4-18, 4-20

## U

---

- UNPREPARED status, 3-21
- UNSIGNED INT
  - external data type, 5-14
- UPDATE\_COUNT\_AVAILABLE status, 3-21, 3-22
- USERID OTT parameter, 8-11

## V

---

- values
  - in context of this document, 4-4
  - in object applications, 4-4
- VARCHAR
  - external data type, 5-14
- VARCHAR2
  - external data type, 5-14
- VARNUM
  - external data type, 5-15
- VARRAW
  - external data type, 5-11, 5-15

## X

---

- XA library, 11-1