



Siebel Sales Handheld Guide

Version 7.7
June 2004

Siebel Systems, Inc., 2207 Bridgepointe Parkway, San Mateo, CA 94404
Copyright © 2004 Siebel Systems, Inc.
All rights reserved.
Printed in the United States of America

No part of this publication may be stored in a retrieval system, transmitted, or reproduced in any way, including but not limited to photocopy, photographic, magnetic, or other record, without the prior agreement and written permission of Siebel Systems, Inc.

Siebel, the Siebel logo, TrickleSync, Universal Agent, and other Siebel names referenced herein are trademarks of Siebel Systems, Inc., and may be registered in certain jurisdictions.

Other product names, designations, logos, and symbols may be trademarks or registered trademarks of their respective owners.

PRODUCT MODULES AND OPTIONS. This guide contains descriptions of modules that are optional and for which you may not have purchased a license. Siebel's Sample Database also includes data related to these optional modules. As a result, your software implementation may differ from descriptions in this guide. To find out more about the modules your organization has purchased, see your corporate purchasing agent or your Siebel sales representative.

U.S. GOVERNMENT RESTRICTED RIGHTS. Programs, Ancillary Programs and Documentation, delivered subject to the Department of Defense Federal Acquisition Regulation Supplement, are "commercial computer software" as set forth in DFARS 227.7202, Commercial Computer Software and Commercial Computer Software Documentation, and as such, any use, duplication and disclosure of the Programs, Ancillary Programs and Documentation shall be subject to the restrictions contained in the applicable Siebel license agreement. All other use, duplication and disclosure of the Programs, Ancillary Programs and Documentation by the U.S. Government shall be subject to the applicable Siebel license agreement and the restrictions contained in subsection (c) of FAR 52.227-19, Commercial Computer Software - Restricted Rights (June 1987), or FAR 52.227-14, Rights in Data—General, including Alternate III (June 1987), as applicable. Contractor/licensor is Siebel Systems, Inc., 2207 Bridgepointe Parkway, San Mateo, CA 94404.

Proprietary Information

Siebel Systems, Inc. considers information included in this documentation and in Siebel eBusiness Applications Online Help to be Confidential Information. Your access to and use of this Confidential Information are subject to the terms and conditions of: (1) the applicable Siebel Systems software license agreement, which has been executed and with which you agree to comply; and (2) the proprietary and restricted rights notices included in this documentation.

Contents

Chapter 1: What's New in This Release

Chapter 2: Overview of Siebel Sales Handheld

About Siebel Handheld 13

Overview of Siebel Handheld Synchronization 14

Siebel Handheld Synchronization Methods and Architecture 14
Handheld Synchronization Servers 14

Overview of Siebel Handheld Client Application Configuration 15

Chapter 3: Application Development

Overview of Siebel Handheld Architecture 17

Unsupported Features for Siebel Handheld 18

Installing the Siebel Handheld Client 20

About Defining User Functionality in Siebel Handheld 20

Configuration Guidelines for Siebel Handheld 21

About Creating Siebel Handheld Projects 22

Designing Screens and Views for Siebel Handheld 22

Configuring User Interface Elements in Siebel Handheld 24

Configuring List Applets for the Handheld Client 24

Configuring Form Applets for the Handheld Client 25

Using Auto Pop-Up Lists in the Handheld Client 26

About Home Page Applets in Siebel Handheld 26

About Buttons in Handheld 27

About the Menu Bar in Handheld 30

About Toolbars in Handheld 30

About the Status Bar in Handheld 31

About Hyperlinks in Handheld 31

Preventing Synchronization Conflicts with Siebel Handheld 32

Recommended Configuration Guidelines for Siebel Handheld 32

Compiling the Siebel Handheld Application 33

Configuring Printing from the Siebel Handheld Application	33
Defining Documents for Handheld	34
Designing Print Applets for Handheld	34
Configuring Applets for Printing for the Handheld Application	35
Configuring Print Buttons for the Handheld Application	35
Creating Print Templates for the Handheld Application	36
Configuring Business Object Filters in Siebel Handheld	36
Enabling Signature Capture in Siebel Handheld	36
Testing the Siebel Handheld Application	38

Chapter 4: Application Administration

Overview of Siebel Handheld Administration Screens	39
Setting Up Users in Siebel Handheld	41
Assigning User Responsibilities to Siebel Handheld Users	41
Administering Siebel Handheld Views	41
Adding Views to the Handheld Application	41
Specifying Views for the Handheld Application	42
Setting Business Component Filters for Siebel Handheld Users	42
Setting Business Object Filters for Siebel Handheld Users	43
Administering Barcode Settings for Siebel Handheld	44
Creating New Barcode Definitions for the Handheld Application	44
Enabling Applications Views for Barcode Scanning	46
About Monitoring Synchronization Sessions for Siebel Handheld	46
Monitoring Synchronization Sessions for Siebel Handheld	47
Obtaining Error Details from Siebel Handheld Synchronization Sessions	47
Obtaining Business Component Information from Siebel Handheld Synchronization Conflicts	48
Obtaining an Audit Trail for Siebel Handheld Synchronization Sessions	48
Acting Upon Synchronization Errors in Siebel Handheld	48
Administering Server Components for Siebel Handheld	49

Chapter 5: Data Filtering

Developing Data Filters for Handheld	51
General and Default Business Object Filters	52
Siebel Sales Handheld Business Object Filters	52

Recommendation for Managing Handheld Business Object Filters	55
Companion Deployments	55
Stand-Alone Deployments	56
Filtering Data for Pick Applets	56
Configuration Directives	57
Examples of Business Object Declarations	58
Designating Visibility	59
Overriding the Popup Visibility	60

Chapter 6: Deployment of Siebel Handheld

Scripting in the Siebel Handheld Client	61
Overview of Server Installation in Support of the Siebel Handheld Client	62
Process of Server Installation for Siebel Handheld Direct Server Sync	64
About Siebel Handheld Synchronization Performance and Scalability	67
Siebel Mobile Web Client Installation	68
Process for Installing the Siebel Handheld Application	68
Editing the Handheld Application Installation Configuration File	68
Enabling Handheld User Database Backup	70
Installing Print Templates in the Siebel Handheld Install Directory	72
Setting up Siebel Handheld Application Installation on a CompactFlash Card	72
Setting the Siebel Handheld Application Restart Parameter	73
Changing the SyncURL on Siebel Handheld Devices	73
Installing the Siebel Handheld Application from External Media	74
Distributing Siebel Handheld Application Patches	74
Deploying Patches to the Handheld Application with Direct Server Sync	75
Deploying Handheld Application Patches with Companion Sync	76
Creating Handheld Application Upgrade Kits to Remotely Deploy Patch Files	77
Downloading Patches to the Handheld Device	77

Chapter 7: Synchronization Conflict Handling and Recovery with Handheld

Preventing Synchronization Transaction Conflicts with Siebel Handheld	79
Extended Pick Processing in Siebel Handheld	79
Enabling Extended Pick Processing in Siebel Handheld	80
Extended Insert Processing in Siebel Handheld	82
Recovering Error Data in Siebel Handheld	84

Chapter 8: Installing the Handheld Application

Preparing To Upgrade From a Previous Siebel Handheld Release	85
Installing on the Siebel Handheld Application	85
Installing Handheld for Companion Sync Users	86
Installing Handheld for Direct Server Sync Users	87
Reinstalling the Siebel Handheld Application	88
Uninstalling the Siebel Handheld Application	89
Preparing the Siebel Handheld Application for Barcode Scanning	89

Chapter 9: Working with Siebel Handheld Applications

Components of the Siebel Handheld Interface	91
Navigating the Siebel Handheld Interface	94
Navigating a List of Records in the Siebel Handheld Application	95
Entering Data with the Siebel Handheld Application	96
Working with Columns in the Handheld Client	96
Finding and Querying Data in the Siebel Handheld Application	97
About Find in Handheld	97
About Queries in Handheld	97
Printing with the Siebel Handheld Application	98
Exporting Data with the Siebel Handheld Application	98
Calendar and Calendar Views in the Siebel Handheld Application	99
Setting User Preferences in the Siebel Handheld Application	100
Backing Up and Restoring Data with the Siebel Handheld Client	100
Synchronizing Data on the Siebel Handheld Device	102
Using Siebel Handheld Synchronization with the Handheld Client	102
Using Companion Synchronization with the Handheld Client	102
Synchronizing the Handheld Client for Companion Sync Users	103
Using Direct Server Synchronization with the Handheld Client	104
Synchronization Troubleshooting with the Siebel Handheld Client	105
Improving Siebel Handheld Application Performance	106

Chapter 10: Using Siebel Sales Handheld

About Using Siebel Sales Handheld	109
About Managing Contacts in Siebel Sales Handheld	109
Scenario for Managing Contacts in Sales Handheld	110

Adding Contacts in Sales Handheld	110
Associating Contacts with Opportunities in Sales Handheld	111
Managing Accounts in Siebel Sales Handheld	111
Scenario for Managing Accounts in Sales Handheld	112
Creating Accounts in Sales Handheld	112
Associating Activities with Accounts in Sales Handheld	113
Associating Opportunities with Accounts in Sales Handheld	114
Developing Opportunities in Siebel Sales Handheld	114
Scenario for Developing Opportunities in Sales Handheld	115
About Creating Opportunities in Sales Handheld	115
About Sales Methods in Sales Handheld	116
Associating a Contact with an Opportunity in Sales Handheld	117
Associating a Product with an Opportunity in Sales Handheld	117
About Opportunity Quotes in Sales Handheld	118
Managing Customer Relationships in Siebel Sales Handheld	118
About Activities in Sales Handheld	119
Scenario for Managing Activities in Sales Handheld	119
Creating Activities in Sales Handheld	119
Delegating Activities in Sales Handheld	119
Associating Contacts with Activities in Sales Handheld	120
Adding General Activities Using the Calendar in Sales Handheld	120
Developing Quotes in Siebel Sales Handheld	122
Scenario for Developing Quotes in Sales Handheld	122
Creating Quotes in Sales Handheld	122
Using Auto Quote in Sales Handheld	123
Adding Quote Items in Sales Handheld	124
Printing Quotes in Sales Handheld	125
Managing Orders in Siebel Sales Handheld	126
Creating Orders in Sales Handheld	126
Adding Order Line Items in Sales Handheld	127
Entering Terms and Totals in Sales Handheld	127
Tracking Expenses in Sales Handheld	128
Creating an Expense Report in Sales Handheld	128
Submitting an Expense Report in Sales Handheld	129

Appendix A: Troubleshooting

Installation	131
Client Installation, Backup, and Restore	131
Synchronization	132

Companion Sync Checklist	132
Direct Server Sync Checklist	132
Re-synchronizing Problems	133
Log Files	133
SQLTrace	135
End User Error Messages	136
Web Server Timeout Errors	136
Performance	136
Siebel Services	139

Appendix B: Screens and Views

Screens and Views	141
-------------------	-----

Appendix C: Business Components and Classes

Supported Business Components for Siebel Handheld	145
Business Component Classes	146
Applet Classes	147

Appendix D: User Properties and Methods

User Properties	149
Global User Properties	149
Methods	150
AutoQuote	150
AutoOrder	151

Appendix E: Print Tagging Language

Overview of Siebel Handheld Print Tagging Language	155
Applet	156
Cell	157
Comment	159
Divider	159
EndOfLine	160
Footer	161
Format	162
GetCount	163
GetDate	163
GetField	164

GetRegistry	165
GetTime	166
GetTotal	166
Header	167
Page Break	168
Picture	168
SetVariable	170
Static Text	170
Title	170

Using Variables in Print Templates	171
------------------------------------	-----

Appendix F: Print Configuration Settings

Overview of Siebel Handheld Print Configuration Settings	173
--	-----

MarginBottom	173
MarginLeft	174
MarginRight	174
MarginTop	174
PaperHeight	174
PaperSize	174
PaperWidth	175
PrinterBaudrate	175
PrinterCompressed	176
PrinterDensity	176
PrinterDither	176
PrinterDraftMode	177
PrinterFormFeed	177
PrinterHandshake	178
PrinterOrientation	178
PrinterPort	178
PrinterType	179
Default Printing Settings	179

Index

1

What's New in This Release

What's New in Siebel Sales Handheld

Table 1 lists changes described in this version of the documentation to support Release 7.7 of the software.

Table 1. New Product Features in Siebel Sales Handheld, Version 7.7

Topic	Description
Signature capture "Enabling Signature Capture in Siebel Handheld" on page 36	You can configure views within your Siebel Sales Handheld application to allow you to capture signatures.
Barcode scanning "Administering Barcode Settings for Siebel Handheld" on page 44	You can set up your Siebel Sales application to capture barcode information with a supported barcode scanner.

2

Overview of Siebel Sales Handheld

This chapter includes the following topics:

- [“About Siebel Handheld” on page 13](#)
- [“Overview of Siebel Handheld Synchronization” on page 14](#)
- [“Siebel Handheld Synchronization Methods and Architecture” on page 14](#)
- [“Overview of Siebel Handheld Client Application Configuration” on page 15](#)

About Siebel Handheld

Siebel Handheld provides a subset of functionality to that of the Siebel Web Client. The Siebel Handheld Client differs from the Siebel Web Client and the Siebel Mobile Web Client in that it uses a selected subset of views, accommodates smaller screen sizes, and has a reduced memory capacity. For a list of functional differences, see [Chapter 3, “Application Development.”](#)

Some features that are available on the Siebel Mobile Web Client are not available on the Siebel Handheld. Scripting and Siebel engines (for example, Pricing and Reporting) are not supported on the handheld. For a list of features that are not supported, see [“Unsupported Features for Siebel Handheld” on page 18.](#)

Some supported features of the Siebel Handheld client are as follows:

- **Application Development with Siebel Tools:** Siebel Handheld applications can be configured in Siebel Tools using the Web Applet Designer. You can take your existing Siebel application and use this as the basis for the Siebel Handheld application, or you can create a new application by using the Siebel Tools application shipped on the Siebel Handheld application DVD. See [Chapter 3, “Application Development,”](#) for more information.
- **Data filtering:** Filtering allows you to specify a subset of data to be used on the handheld device. Filtering is an important feature of a Siebel Handheld deployment because of the relatively large size of the average enterprise database in comparison to the relatively limited memory capabilities of handheld devices. It is important that you allocate sufficient time in the project plan to create and test the handheld filters. See [“Application Development” on page 17](#) for more information.
- **Deployment options:** The Siebel Handheld application can be installed on Windows-powered devices in one of two ways. The first is to create a partnership between a desktop or laptop PC and the handheld device using Microsoft ActiveSync. The second is to install the Siebel Handheld application from external media, for example, a Cabinet (CAB) file. Handheld patches can be remotely deployed using PatchAgent. For more information, see [Chapter 6, “Deployment of Siebel Handheld.”](#)

- **Patch Updates.** Siebel Handheld automatically applies the latest software patches to the handheld device when needed. Companion Sync allows users to Synchronize the Handheld Database to the local database on Companion PC and invokes Siebel Remote to synchronize the local database with the server database.
- **Backing Up and Restoring Data:** The Siebel Handheld application provides database backup functionality. A database restore utility is also included with the application. See [Chapter 4, "Application Administration,"](#) and [Appendix A, "Troubleshooting,"](#) for details.

Overview of Siebel Handheld Synchronization

The Siebel Handheld Synchronization (Sync) client synchronizes data between the Siebel Handheld database and the Mobile Web Client database or server database. The synchronization process does the following:

- Updates the Siebel server database with changes made to the Siebel Handheld database
- Updates the database on the handheld device with changes made to the Siebel server database
- Downloads metadata changes, such as object definitions for new or modified screens or views
- Allows users to select filters to limit the amount of data that is downloaded
- Automatically applies the latest software patches to the handheld device when needed

Siebel Handheld Synchronization Methods and Architecture

The following methods can be used to synchronize data on the handheld device with data in the Siebel server database: Companion Sync (CS), Direct Server Sync (DSS) and Direct Server Sync by means of Proxy (DSSvP). The architecture of these methods is discussed in the following sections.

Handheld Synchronization Servers

There are two types of synchronization servers: direct synchronization servers and companion synchronization servers. A direct synchronization server run on the Siebel application server can accept concurrent synchronization requests from multiple synchronization clients. When connecting to a direct synchronization server, the Siebel Handheld Sync client synchronizes its data with the server-side database. Companion Sync allows users to synchronize the Handheld Database to the local database on a companion PC device and invokes Siebel Remote to synchronize a local database with the server database.

In Direct Server Sync mode, the Siebel Handheld Synchronization client uses the HTTP protocol over a network connection to communicate with the handheld synchronization server. Users should configure their handheld devices for communication over the desired network.

A companion synchronization server runs on a companion personal computer with a Mobile Web Client installation and supports synchronization with a data source specified in a client configuration; the database resides on the companion PC.

Companion Sync

Companion Sync allows users to synchronize the Siebel Handheld application and database with a Siebel Remote database on a Mobile Web Client.

Microsoft ActiveSync is used to connect the handheld device and the companion PC through a serial or USB connection or through a network connection. The user launches Siebel Handheld Sync from companion PC or the device. The user can change the default filters using Siebel Handheld Sync.

Direct Server Sync

Direct Server Sync allows users to synchronize their Siebel Handheld application and database directly with the Siebel server. The user connects the handheld device to the Siebel application server through a network connection that uses the HTTP protocol. The connection runs through a IIS Web server to the Siebel Gateway Name server and application server, where the Sync server components are installed and running.

Direct Server Sync by Means of Proxy

Direct Server Sync by means of Proxy (DSSvP) allows users to synchronize their Siebel Handheld application and database directly with the Siebel server. The user connects the handheld device to the Siebel application server through ActiveSync and the network connection established by the companion PC. The connection runs through a IIS Web server to the Siebel Gateway Name server and application server, where the Sync server components are installed.

Overview of Siebel Handheld Client Application Configuration

The following provides an overview of the configuration process of the Handheld client. Complete the following steps to configure your handheld client application.

To configure the Siebel Handheld client

1 Define the user functionality.

Determine which user interface elements (such as screens, views, toolbars, applets, find, and help) will be necessary for your Siebel Handheld Client end users. For more information, see ["About Defining User Functionality in Siebel Handheld"](#) on page 20.

2 Configure the Siebel Handheld Client user interface.

The process for configuring user interface elements in the Siebel Handheld Client is the same as that for other Siebel clients. For more information, see ["Configuring User Interface Elements in Siebel Handheld"](#) on page 24 and *Configuring Siebel eBusiness Applications*.

3 Identify all eScript or VB script.

Siebel Handheld applications do not currently support scripting, including eScript or VB script. Scripting used in your Siebel application may conflict with your Siebel Handheld application configuration.

4 Compile the new configuration.

For more information, see ["Compiling the Siebel Handheld Application" on page 33](#).

5 Test the new configuration.

Test the configuration, repeating the previous steps, to address any configuration errors.

After completing the Siebel Handheld Client configuration, you are ready to install it on the handheld devices. To install the Siebel Handheld configuration on a handheld device, see the instructions in ["Installing on the Siebel Handheld Application" on page 85](#).

3

Application Development

This chapter includes the following topics:

- "Overview of Siebel Handheld Architecture" on page 17
- "Unsupported Features for Siebel Handheld" on page 18
- "About Defining User Functionality in Siebel Handheld" on page 20
- "Configuration Guidelines for Siebel Handheld" on page 21
- "About Creating Siebel Handheld Projects" on page 22
- "Designing Screens and Views for Siebel Handheld" on page 22
- "Configuring User Interface Elements in Siebel Handheld" on page 24
- "Preventing Synchronization Conflicts with Siebel Handheld" on page 32
- "Recommended Configuration Guidelines for Siebel Handheld" on page 32
- "Compiling the Siebel Handheld Application" on page 33
- "Configuring Printing from the Siebel Handheld Application" on page 33
- "Testing the Siebel Handheld Application" on page 38

Overview of Siebel Handheld Architecture

The process for configuring a Siebel Handheld Client has a few differences, described in this chapter, from the process for configuring other types of Siebel clients.

NOTE: Readers should familiarize themselves with the Siebel client configuration process described in *Configuring Siebel eBusiness Applications* before attempting to configure the Siebel Handheld Client.

The five layers in the Siebel Handheld architecture are comparable to those used on the Siebel Web Client:

Application layer. The application layer starts and closes the application.

User Interface layer. The user interface layer renders the display and interacts with actions of the user.

Object Manager layer. The object manager layer provides a consistent object behavior and interaction between all business objects within the application.

Data Manager layer. The data manager layer maintains an object-oriented abstraction of the native data stored in the data repositories for the benefit of the object manager.

Database layer. The database layer includes the data that Siebel Handheld users access.

Your Administrator configures an application on the Siebel client using Siebel Tools and compiles the Siebel repository (.srf) file. During the synchronization process, information specific to the Siebel Handheld Client is extracted from the Siebel repository file. This information is used to create a repository metalanguage (.rml) file, that is downloaded to the handheld device. The repository metalanguage file has all of the layout information for the handheld device. For more information on Siebel Tools, see *Using Siebel Tools*.

Unsupported Features for Siebel Handheld

The differences between configuring user interface elements for the Siebel Web Client and the Siebel Handheld Client are shown in [Table 2](#).

Table 2. Configuring Siebel Client User Interface Elements

Client	Siebel Tools	SWT Template Files	Specialized Algorithms
Siebel Web Client	Yes	Yes	No
Siebel Handheld Client	Yes	No	Yes

The following are not supported in Siebel Handheld applications:

- The following applet types are not supported:
 - Chart
 - Explorer
- More than two applets per view is not supported. A maximum of two applets may be displayed at one time.
- Group boxes are not supported. See [“Group Boxes” on page 26](#) for information on how to accommodate this limitation.
- Alarm Manager is not supported. Therefore, if an alarm check box is added to an applet and the check box is selected, no alarm sounds.
- The base time zone is determined by the system settings on the server and cannot be changed on the handheld device.
- Alphabet tabs are not supported.
- Scripting is not supported. However, any scripts on the business components will be executed during synchronization.
- Siebel Workflow is not supported.
- Assessment creation is not supported.

See the following topics which outline, more specifically, other unsupported features.

Multi-Value Groups (MVG)

The Multi-Value Group applet is not supported on the Siebel Handheld Client; however, the Multi-Value Group relationship is supported. The Multi-Value Group (MVG) control button does not appear on fields in Siebel Handheld Client applications. Instead, MVGs can be implemented as parent-child views. As a result, MVG fields are not editable within the parent record. In the Siebel Web Client, addresses of accounts are added, deleted, or edited through the Business Address MVG applet. However, in the Siebel Sales Handheld Client, these functions must be done through a Business Address child applet with an Account applet as its parent.

On the handheld, all MVG fields are displayed as read-only fields with the primary record visible. If you have an application or business requirement that requires the user to view or update all the records in the MVG, you must configure a separate view for that MVG. For example, the Address field in the Accounts or My Accounts view is an MVG. In the Siebel Handheld Client that field is read-only and displays the primary record. In order for the handheld user to see and update the addresses, the new Address view is configured in Siebel Tools. This new Address view is visible in the Show drop-down list.

Functions

Siebel Handheld applications support most of the calculated fields and operations used in the Siebel Web applications with a few exceptions. See [Table 3](#) for a list of the unsupported functions.

Table 3. Unsupported Functions

Function Name
BCHasRows
DockingNodeId
DockingNodeName
DockingNodeRoutId
EAILookupExternal
EAILookupSiebel
EXISTS
GetHQInstanceId
GetHQInstanceName
GetNumBCRows
GetProfileAttr
GetXAval
IsDocked

Table 3. Unsupported Functions

Function Name
LanguageName
LocaleName
LookupMessage
LookupTranslation
NOT
RepositoryId
RepositoryName
RowIdToRowNum
ToolsLanguage

The NOT key word is not supported on Booleans. Use the != operator instead. For example, "Active" != "Y".

The RowIdToRowNum function is supported differently in the handheld applications than in the Web applications. In Web applications, RowIdToRowNum converts a row Id to a numeric value. In the handheld applications, it returns the row ID itself.

Installing the Siebel Handheld Client

For information on installing the Handheld client, see [Chapter 6, "Deployment of Siebel Handheld."](#)

About Defining User Functionality in Siebel Handheld

The first step in configuring a Siebel Handheld Client is to determine which user interface elements are necessary. Siebel Handheld Client users have different requirements from Siebel Web Client users. Keep in mind the differences in display size, memory capacity, and input methods between handheld devices and larger computers, such as desktop computers.

The goal is to create applications that are easy for your end users to use and which take advantage of the strengths of the handheld device platform. Because of processing speed, memory limitations, and form factor differences, you should only include those user interface elements that are necessary for users to complete their job responsibilities.

Configuration Guidelines for Siebel Handheld

There are a few general guidelines you should bear in mind when configuring for the Siebel Handheld application. Use these guidelines when you design any new objects for the Siebel Handheld Client. This approach facilitates a logical separation of the Siebel Handheld Client user interface elements from the Siebel Web Client user interface elements.

■ Identify User Activities

To conserve memory (and thereby improve performance) and ease navigation, identify business processes that are required by end users and develop applications that support these processes. If more than one type of user needs a Siebel Handheld Client application, it is preferable to divide the application into multiple responsibilities rather than give all possible users access to all available screens and views. Responsibilities are fully configurable by the application developer.

■ Limit the number of screens and views

Limit the number of screens and views. Determine critical business processes that the handheld will support and only pick the views that are necessary and make sense based on business requirements.

■ Limit the number of applets for each view

Design each view so that it has one or, at most, two applets. Limiting the number of applets enhances performance, and enriches the user experience.

NOTE: In some instances, Siebel Systems found it necessary to create a view with three applets in its handheld applications. For these views, a toggle button was added to the applet so that the user can easily navigate between the two child applets.

■ Limit the number of columns and fields for each applet

Design each applet so that it only contains columns and fields that are required for end-user tasks.

■ Design applications that contain as few screen and view hierarchy levels as possible

In a Web-based application, you may have views with many applets, and the user toggles between the applets. However, for handheld applications, create a larger number of views with fewer applets to allow users to quickly find information with a minimal amount of toggling.

■ Design for the Handheld Screen

Consider the following questions when designing your applets:

- If you are using a list applet, how wide is that list applet going to be?
- What are the most important fields and columns that a user needs to see at a glance before scrolling?
- If you have a form applet that is a parent, for example, what fields do you really need in order to avoid scrolling?
- Because there is less screen space on a handheld device than on a laptop or desktop, the most important data should be immediately visible.

About Creating Siebel Handheld Projects

The Siebel Handheld projects appear in the list of projects in Siebel Tools; when Project is selected in the Object Explorer, the list of projects is displayed in the Object List Editor.

Use a naming convention that allows you to easily identify applications, screens, views, and applets belonging to a particular Siebel Handheld application. This allows you to locate all the object definitions in a Siebel Handheld application by querying on the name in the Object List Editor. For example, all of the Siebel Handheld Client screens, views, applets, toolbars, and menus use either an SHCE prefix (for example, SHCE Sales Account List View) or a CE suffix. Use the Object List Editor to query for views that contain the prefix SHCE or the suffix CE; doing so displays all of the Siebel Handheld Client views.

If you create a new Siebel Handheld application, create a new suffix or prefix to identify the name of the application and each screen, view, and applet name. For example, you could use PPC_SHCE for an application.

Designing Screens and Views for Siebel Handheld

Each view in a Siebel Handheld application can display a maximum of two applets at a time, regardless of the number of applets in the view. If there are more than two applets in a view, the user can navigate to additional applets by toggling.

Screen Allocation

The amount of screen space available for applets is determined by the type of applets in the view. Two applets are stacked above one another. A parent form applet in a two-applet view displays multiple fields on a screen. Users use the scroll bar to navigate. The form applet dynamically resizes if there are fewer than five fields and, therefore, does not waste screen display space with empty lines. The maximum number of fields that are displayed at one time is configurable by setting the Max Parent Applet Size preference in the User Preferences dialog. See ["Setting User Preferences in the Siebel Handheld Application"](#) on page 100 for more information on this user preference.

Toggling Between Multiple-Applet Views

The Siebel Handheld Client application displays up to two applets at one time. If the view has only one applet, the applet takes up the entire display area. For views with two or more applets, the first two applets in the view are displayed, and the user toggles to see the other applets. The first applet is always displayed and the second applet changes as you toggle.

By default, the user toggles by choosing the View > Toggle menu item. In addition, it is recommended that you provide a toggle button as a visual cue to the end user that there are additional applets. Add a toggle button to each applet except the first applet. Identify the button with a Toggle caption and set methodInvoked to ToggleApplet.

Drill-down Only Views

Some views may be drill-down only views—that is, they can only be accessed by navigating from another view. These views should not be accessible through the Show drop-down list. However, when the end user navigates to the view, the view title appears in the Show drop-down list. To configure a drill-down only view, set the view title as you would for any other view and set the ScreenMenu property to FALSE. See *Configuring Siebel eBusiness Applications* for more information.

Applet Focus Behavior

When navigating between views, there may be instances when you need to override the default behavior for giving focus to an applet

The GotoView method is used to navigate from one view to another. A button control is added to the applet in the view you want to navigate from, the button's methodInvoked property is set to GotoView and the button's View property is set to the view that is to be created. When the GotoView method is executed, it builds the specified view. If the view includes a parent and child applet, GotoView gives focus to the child applet. This is the desired behavior in most instances when you are simply navigating from one view to another.

If the desired behavior is to navigate to a new view and, additionally, create a new record, then you must use the GotoViewNewRecord method. This method calls two methods; it calls GotoView, and then it calls NewRecord, which creates a new record in the new view.

In some instances the default behavior of these methods does not produce the intended behavior. For example, in the Orders view of the Service Requests screen, when you tap the Create New Order button, it takes you to the Order Details view, which contains a parent form applet (Service Request Order) and a child list applet (Service Order Entry Line Item). In this instance, when the Create New Order button's GotoViewNewRecord method is executed, you want a new order to be created. However, the default behavior is to give focus to the child applet rather than creating a new record in the parent applet. Therefore, you need to override the default behavior of GotoView with the control user property OverrideDefaultApplet, and set the value to the applet that you want to give focus. The valid values are 0 (parent) and 1 (child). For example, if you create a button labeled "Create Service Request Order," you would define user properties shown in [Table 4](#):

Table 4.

Name	Value
View	SHCE Service Order Line Items View
OverrideDefaultApplet	0

Views with Associated Print Templates or Reports

Print templates are text files that you design and create for printing. After creating a print template, you associate it with an applet. When an end user chooses to print a view, the print template that is associated with the applet is automatically selected and used for printing. Follow these guidelines when creating print templates:

- Only one print template can be associated with an applet.

- The print template name for a particular display applet is registered in the Mail Template property in the Applet object associated with the applet.
- The template must be placed in the Templates directory.
- The template name that goes into the Mail Template property should not include a path name or extension. For example, if the full path of the template is `\Program Files\Siebel Handheld\Templates\InvoiceTemplate.txt`, you would enter only the root name `InvoiceTemplate` in the property field.
- The template file itself must have a `.txt` extension on the device.

For more information, see [Appendix F, "Print Configuration Settings."](#)

Configuring User Interface Elements in Siebel Handheld

When configuring user interface elements on the Siebel Handheld Client, also consider the processing speed and memory constraints of handheld devices. The constraint on processing speed affects the performance of a handheld device. The performance of a handheld device is also related to the number of screens and views downloaded to the handheld device. Because handheld devices are not meant to provide the same functionality as larger devices, such as laptops, the number of screens and views must be kept to a minimum on the handheld device.

Due to size constraints on handheld devices, the Siebel Handheld Client displays user interface elements differently from the Siebel Web Client. Consider these differences when configuring the Siebel Handheld Client application. For example, Siebel Handheld Client does not support an alphabetical index.

Configuring List Applets for the Handheld Client

You configure list applets and list columns for Siebel Handheld applications the same way you configure them for other Siebel applications.

Recommended Strategy for Configuring List Applets

The recommended strategy when configuring the Siebel Handheld Client is to use the list applets for record navigation and to rely on form applets to provide the record details.

The following are additional guidelines to follow when designing list applets:

- Configure specific list applets for your Siebel Handheld application, rather than reusing Siebel Web Client list applets.

- Remove all but the essential list columns. Because there is limited screen area to display list columns, omit all unnecessary columns to minimize horizontal scrolling.

You may either remove the columns from the application or set the Show in List property on the column to FALSE. These two methods are different in the following ways. If the columns are removed from the application, these data won't be downloaded to the handheld device, which keeps the handheld data and a minimum and, in turn, optimizes synchronization performance. If the Show in List property on the column is set to FALSE, the data is still downloaded to the device but is not shown by default. This second approach, though without the synchronization optimization benefit, does allow convenience for the user who wants to customize visible columns. You should take these concerns into account when setting up users.

- Reorder the remaining list columns so that the most frequently used columns are furthest to the left.
- Reduce the default width of the list columns so that more columns can be viewed at one time.
- Use hyperlinks to ease navigation by enabling users to drill into a form applet.

These changes can minimize the amount of horizontal scrolling and column reordering that users must do. Limiting the number of list columns to those that are essential minimizes the amount of data downloaded to the device, resulting in faster synchronization times and more economical use of device memory.

NOTE: All required fields on form and list applets appear with an asterisk (*). If an administrator specifies that a field is required, the field appears with an asterisk in the user interface.

Use Siebel Tools to modify, or rearrange List Columns. For more information on the List Column options, see *Configuring Siebel eBusiness Applications*.

You may make columns available, but not visible by default, by setting the Show In List property of the column to FALSE. From the Siebel Handheld application, you can make the columns visible from the View > Columns Displayed menu option. In order for the change to be reflected in the application, you must compile the application and synchronize with the handheld device. In addition, you must delete the \Program Files\Siebel Handheld\siebel.ssf file on the handheld. If this file is not deleted, the change to the Show In List parameter is not reflected in the application.

Configuring Form Applets for the Handheld Client

The handheld uses a specialized algorithm to format and display form applets. Due to the display limitations on the device, only one pair of label and field controls are displayed on each row of the form, regardless of the layout shown within Siebel Tools.

Layout Sequence

When configuring for the handheld device, the Applet Web Template Items in the Applet Web Template determine the controls that appear on a form applet. The layout of form applets on the handheld device is determined by the HTML Sequence field set on control objects.

The HTML Sequence field determines the screen layout of a handheld device. Controls are ordered from top-to-bottom based on their HTML Sequence property values. Label and control pairs that do not fit on the same line as other label and control pairs wrap to the next line.

Labels

Keep field labels in applications short (approximately 12 characters or fewer, depending on the character width). Use abbreviations where possible. Labels that are too long are truncated.

Group Boxes

Group boxes are not supported and are not displayed in form applets, even if they are added in the Web Applet Designer. Therefore, reword the field labels to include group box information if necessary. For example, you may have two group boxes on the form, one labeled Ship To and another labeled Bill To. Each group box includes a field named Address. Because group boxes are not supported, the Ship To and Bill To labels are lost, and two fields with the identical Address label remain. Therefore, you must rename the Address labels "Ship To Addr" and "Bill To Addr," or some other label that distinguishes them.

Using Auto Pop-Up Lists in the Handheld Client

Sometimes when a user encounters a new view, he or she must perform an action, such as filling in a required field by selecting a value from a pop-up list. Rather than requiring the end user to tap the control to open the pop-up list, you can configure the view so that the pop-up list automatically opens when the end user gets to that view. To configure a pop-up list to open automatically, add the user property on the applet with Name set to AutoPopupField. Depending on the type of applet, this property is set differently:

- For list applets, set the AutoPopupField property to the Business Component field name.
- For form applets, set the AutoPopupField property to the name of the control.

About Home Page Applets in Siebel Handheld

To configure a Home Page applet, create an applet that has controls of HTML Type Button only. Use the following guidelines in creating your Home Page applets:

- Set the MethodInvoked property of these controls to GotoView. Then add a user property for the control, and set the Name parameter to "View" and set the Value parameter to the view name.
- Set the Caption field.
- Set the HTML Sequence field according to the order in which the buttons are laid out on the device. The buttons appear on the Home Page applet of the handheld device, laid out in rows of three buttons.
- Set the class property of the Applet to CSSFrameCEHome.

About Buttons in Handheld

Set the HTML Type field on buttons to Button, MiniButton, PushButton, or MiniButtonEditNew. All of these HTML Types map to the same button control on the handheld device.

Buttons with text labels on them are sized to the minimum width required to fit the text on the buttons.

NOTE: You cannot use scripting to augment the button functionality in handheld applications.

You may add buttons as long as the method invoked is supported by the class or superclass of the frame or business component. You may also remove buttons from an applet. Be careful when removing buttons because you may alter the behavior of your application in unintended ways. [Table 5](#) describes the behavior of buttons on the different screens. Use this table to guide your decisions about removing buttons from your handheld applications.

Table 5. Button Functionality

Screen	View	Button	Button Functionality
Billings	Invoice Line Items	Cancel	Only applies to Invoices in which Type = Receivable. <ul style="list-style-type: none"> ■ Changes the invoice status to Cancelled. ■ Changes the Order status to Open. ■ Opens the Order Line Items view. If the order cannot be found, displays a warning message.
Billings	Invoice Line Items	Pay	Opens the Invoice Payments view.
Billings	Invoice Line Items	Print	Prints an invoice.
Billings	Invoice Line Items	Visit Home	Opens the Outlet Visits view, Activities screen. The focus is on the visit in progress for the account on the invoice.
Billings	Invoice Payments	Print	Prints a payment receipt.
Billings	Invoice Payments	Visit Home	Opens the Outlet Visits view, Activities screen. The focus is on the visit in progress for the account on the invoice.

Table 5. Button Functionality

Screen	View	Button	Button Functionality
Billings	Invoice Line Items	Deliver	<p>If Type = Receivable:</p> <ul style="list-style-type: none"> ■ Checks the inventory to see if there is sufficient stock to fill the order. If the requested quantity exceeds the on-hand stock, a message is displayed informing the user that there is insufficient inventory. ■ Compares the order total against the account's available credit. If the order exceeds the available credit, a warning message is displayed. ■ Changes the invoice status. ■ Decrements inventory. ■ Decrements available credit. <p>If Type = Payable:</p> <ul style="list-style-type: none"> ■ Creates a credit memo. ■ Increments inventory by the total quantity shipped. ■ Changes the invoice status to Credited.
Orders	Order Line Items	Invoice	<ul style="list-style-type: none"> ■ Checks the inventory to see if there is sufficient stock to fill the order. If the requested quantity exceeds the on-hand stock, a message is displayed informing the user that there is insufficient inventory. <p>The user is asked if he or she wants to update the order based on the available quantity. If the user chooses to continue, the system adjusts the Qty and Bonus Qty fields so that the totals do not exceed the available stock.</p> <p>Otherwise, the user is returned to the Order Line Items view where he or she can edit the quantities.</p> <ul style="list-style-type: none"> ■ Compares the order total against the account's available credit. If the order exceeds the available credit, a warning message is displayed. ■ Changes the order status to Billed. ■ Generates an invoice for the order. ■ Cleans the order of all zero-quantity items. ■ Opens the Billings screen, Invoice Line Items view.

Table 5. Button Functionality

Screen	View	Button	Button Functionality
Orders	Order Line Items	List Products	Lists all products in the account's Product Distribution list that are flagged as orderable (Retail Order flag).
Order	Order Line Items	Print	Prints the order.
Outlet Visits	My Outlet Visits	End Visit	<ul style="list-style-type: none"> ■ Records the current timestamp in the Actual End field. ■ Changes the status. ■ Makes the record read only. ■ Calculates the actual duration of the visit.
Outlet Visits	My Outlet Visits	Prepare Visits	<ul style="list-style-type: none"> ■ Verifies that a retail order activity is assigned to a selected visit. ■ If a retail order activity exists, an order header is created for the account and products that are flagged as orderable for the account are listed as line items in the order. ■ If a retail order product does not exist for the selected visit, an order header is created for the account.
Outlet Visits	My Outlet Visits	Start Visit	<ul style="list-style-type: none"> ■ Records the current timestamp in the Actual Start field. ■ Changes the status. ■ Opens the Visit Activities view.
Outlet Visits	Visit Activities	End Activity	<ul style="list-style-type: none"> ■ Records the timestamp in the Actual End field. ■ Changes the status. ■ Makes the record read only.
Outlet Visits	Visit Activities	End Visit	<ul style="list-style-type: none"> ■ Records the current timestamp in the Actual End field. ■ Changes the status. ■ Makes the record read only. ■ Calculates the actual duration of the visit.

Table 5. Button Functionality

Screen	View	Button	Button Functionality
Outlet Visits	Visit Activities	Start Activity	<ul style="list-style-type: none"> ■ Records the current timestamp in the Actual Start field. ■ Changes the status. <p>Opens one of the following views:</p> <ul style="list-style-type: none"> ■ If Type = Retail Assessment, opens the Accounts screen, Assessments view. ■ If Type = Retail Audit, opens the Retail Audit view. ■ If Type = Retail Order, opens the Orders screen, Order Line Items view. ■ If Type = Stock Transfer, opens the Activities screen, Product Movement view. ■ If Type = Review Billings, opens the Accounts screen, Invoices view. ■ If Type = Return Order, opens the Accounts screen, RMAs view.
Outlet Visits	Visit Activities	Start Visit	<ul style="list-style-type: none"> ■ Records the current timestamp in the Actual Start field. ■ Changes the status.
RMAs	RMA Line Items	Credit	<ul style="list-style-type: none"> ■ Changes RMA status to Billed. ■ Generates a credit note. ■ Opens the Billings screen, Invoice Line Items view.

About the Menu Bar in Handheld

The menu object definition in the Siebel repository that is implemented in handheld applications is named SHCE Generic. The default menu bar configuration for the Siebel Handheld Client includes the following menus: File, Edit, View, and Help. You may remove or rename menus on the menu bar, but you cannot add new menus. You may reorder the menu items by changing the Position property for the menu items. Generally, use the default menu bar configuration for all of your Siebel Handheld Client applications.

About Toolbars in Handheld

This section describes how to configure the toolbar for your application.

Table 6 shows the supported toolbar functions.

Table 6. Supported Toolbar Functions

Toolbar Functions
Back, Forward
New Record
New Query, Execute Query
Next Record, Previous Record, First Record, Last Record
Minimize/Maximize
Delete Record

The default toolbar can be configured in Siebel Tools by configuring the SHCE Main toolbar object. SHCE Main is the main toolbar that is downloaded to the handheld device. If a toolbar named SHCE Main does not exist in your repository, a default toolbar, *Main*, is downloaded instead.

The SHCE Main toolbar contains the default buttons for the device: Back, Forward, New Record, New Query, and Execute Query. Change the order of the buttons on the display by modifying the Position property of the toolbar items. Remove a toolbar button by deleting it or making it inactive.

You can add additional default buttons to the toolbar by creating toolbar items whose Command property matches the name of an active bitmap in the SHCE Command Icons bitmap category. Do not add bitmaps to the SHCE Command Icons bitmap category because only those commands, which are already provided, are supported on the device. No additional commands are supported. You can remove a bitmap or make a bitmap inactive if you do not want it to appear in the Customize Toolbar dialog box.

You can change the bitmap for a toolbar by reimporting the bitmap from the SHCE Command Icons bitmap category.

An end user can personalize the toolbar by selecting View > Toolbar.

For more information on toolbars, refer to *Configuring Siebel eBusiness Applications*.

About the Status Bar in Handheld

The status bar is located above the toolbar. The status bar displays the status of an applet with focus, including the applet title and record item count (for example, Contacts: 1 of 13).

About Hyperlinks in Handheld

Configuring a drilldown, or clicking a hyperlink or dynamic hyperlink in the Siebel Handheld Client, is performed the same way as with other Siebel clients. For more information on configuring drilldowns, see *Configuring Siebel eBusiness Applications*.

Preventing Synchronization Conflicts with Siebel Handheld

Because multiple users are synchronizing with the server, conflicts may occur when any single user synchronizes his handheld. For more information on how to configure your application to prevent synchronization conflicts, see [Chapter 7, “Synchronization Conflict Handling and Recovery with Handheld.”](#)

Recommended Configuration Guidelines for Siebel Handheld

The Siebel Handheld Client application performs best if you use the following guidelines:

- Keep the number of views in your application to 30 or fewer.
- For optimal usability, limit each view to one or two applets.
- To minimize horizontal scrolling, limit the number of columns displayed in a list applet to no more than ten.
- There is no limit on the number of fields in form applets of single-applet views. However, to minimize scrolling, keep the number of fields to 20 or fewer.
- For each screen, create a view called My * or All * as a single list-applet view. For example, for the Activities screen, create a My Contacts view that has the Contacts list applet only.
- For each screen, create a single-applet More Info view. Create this applet as a form applet. For example, for the Contacts screen, create a More Info view that has the Contacts form applet only.
- Use a form applet for the parent for each parent-child view.
- In a multi-applet view, limit the number of fields in form applets to five or fewer. Add additional fields only if the field width is short—for example a check box field. Reduce the number of fields if the fields are multiline—for example, a Comments box that contains three lines of text.
- Do not include read-only check boxes in form applets. It is very difficult for users to discern that the check box is not editable.
- Limit the number of views within a screen to 12 or fewer so that the View drop-down list is not too long and unwieldy.
- Limit the number of screens to six or fewer so that the Screen drop-down list is not too long and unwieldy.
- Keep query names to about 15 characters or fewer, so that they fit in the Queries drop-down list. For example, North American Organization is too long for a query name, so you should change it to a shorter name, such as N. American Org. The number of characters is a general guide because characters vary in width (for example, W is wider than i).
- Keep screen names to about 15 characters or fewer, so that they fit in the Screen drop-down list. The number of characters is a general guide because characters vary in width.

- Keep view names to about 30 characters or fewer so that they fit in the View drop-down list. The number of characters is a general guide because characters vary in width.
- Limit the size of the dbfile.txt file to less than two megabytes (MB). The RDBMS on the handheld device is approximately three times the size of dbfile.txt. If the data files are so large that they cannot be imported into the database with the available memory, users cannot successfully synchronize their data.

Compiling the Siebel Handheld Application

Compiling the repository for the Siebel Handheld Client is identical to compiling on the Siebel Web Client *Using Siebel Tools*. Perform a full compilation the first time; subsequent compilations can be incremental, replacing only the projects that are affected. This assumes that you have organized all of your handheld object definitions in one project or a limited set of projects.

When you compile your application, a Siebel repository file (.srf) is created and put in the destination directory you specified during the compile procedure. Make this .srf file the source of repository information for the Siebel Handheld test client machine, defining all Siebel applications for that client, when you move it to your local \Siebel\objects directory.

It is strongly recommended that you make a backup of the existing .srf file in your local \Siebel\objects directory before overwriting it with the new one. That way, if you make an error or you want to revert to the original application, you have a backup that you can easily restore. For more information, see *Using Siebel Tools*.

Configuring Printing from the Siebel Handheld Application

Users may print from any view in the application. However, they are not necessarily printing what they see on their screen. They may print a portion of the data they view or data that is not viewable at the time.

A print template defines the document that is to be printed. After the template has been defined, it must be associated with an applet in a view.

This section provides information on the following topics:

- Defining documents
- Designing print applets
- Configuring applets for printing
- Creating print buttons
- Creating print templates

Defining Documents for Handheld

Defining documents for printing includes several steps:

- Determine the documents your users need to print.
- Determine the views from which they are most likely to print the documents.
- Lay out the document for printing.

Determining which documents users will need and the views from which they are most likely to print requires that you have a good understanding of the users' day-to-day work.

Whether the existing applets in a view include most of the required data or only a small portion is a secondary consideration. It is not likely that a printout of the existing applets, which are formatted for an electronic PDA interface, will provide an acceptable or usable printed document. In most instances, you need to create additional applets that are specifically used for printing data.

The printed document will be composed of several applets which are added to the view. The applets pull the data from the underlying business components. These applets, in turn, direct the data to the print templates discussed in [Appendix E, "Print Tagging Language."](#)

Designing Print Applets for Handheld

The print template references applets associated with the view and is how you specify what data appears in the printed document. For information on print templates, see "[Creating Print Templates for the Handheld Application](#)" on page 36. As you design your applets, you should be aware of the print specifications of the printers used in the field. Portable printers typically print on two-inch or four-inch wide paper. You need to design your applets so that the data fits within the limits of the paper width. Keep your documents simple so that they work with different sizes of paper. The following are some guidelines to use when designing your applets to accommodate the smaller paper sizes.

Form Applets

Data from only one business component can be displayed on each line in your document. When you design your form applets, keep in mind that you can display a maximum of two columns of data in form applets. You can specify that each column of data is preceded by an optional caption column. This means you can have up to four columns displayed in your document—two data columns and two caption columns. Alternatively, you may have no captions, and simply display one or two columns of data.

The ratio between caption and data columns is, respectively, 35 percent and 65 percent. This is a fixed relationship that cannot be customized in the template.

List Applets

When specifying the width of a column, you can either specify it with a unit of measurement or as a percentage of the total page width. For example, you can specify that the first column is 20 mm, and the second column is 40 mm. If the width of the paper you print to is narrower than 60 mm, the column widths automatically adjust to fit the printable width as a proportion of the specified width. Therefore, the first column will always be 33 percent, and the second column will be 67 percent of the paper width. The minimum width for a column is 8 mm, which includes a 3 mm gutter margin between columns.

You can specify any number of columns in your list applet. However, if the width of the column is less than 8 mm, the application ignores the column and does not print it.

On narrow paper widths, data from a field may not all fit on one line. Data that does not fit can be specified, in the Applet tag, to wrap to the next line and keep wrapping until the data in that field is completely displayed. The printable width of the page is equal to the paper width minus the left and right margins ($\text{PaperWidth} - [\text{LeftMargin} + \text{RightMargin}]$). These parameters are set in the setup.ini file. For more information on setting these parameters, see [Appendix F, "Print Configuration Settings."](#)

Configuring Applets for Printing for the Handheld Application

Configure print applets as you would any other applet using Siebel Tools. In addition, set the following properties for each applet in the view.

- Set the HTML Popup Dimension value to 0x0.

The 0x0 setting hides the applet from the end user who should not see the applet that is used to generate the document. Exposing these applets would complicate a product that is tightly configured for an effective and efficient workflow on a small mobile device.

NOTE: For compatibility with previous versions, Siebel Systems continues to support the name, *Popup Dimension*, for this property. However, it is recommended that you use *HTML Popup Dimension*.

- Set the name of the Mail Template to be the name of the print template file. For more information on the print template file, see ["Creating Print Templates for the Handheld Application"](#) on page 36. For more information on the Mail Template property, see ["Views with Associated Print Templates or Reports"](#) on page 23.

Configuring Print Buttons for the Handheld Application

While users can use the File > Print menu option to print a document, it is helpful to include a Print button on the applet to give users a visual reminder that it is possible to print from a particular view.

When you design your applets, keep the following in mind when deciding where to place the print button:

- Add the print button to the applet that is visible to the user. Do not add the print button to the print applet, which the user never sees.
- Consider what the desired behavior is when determining the placement of a print button.

For example, in a parent-child view, you may want to add the print button to the parent applet to ensure that the print button is always enabled. This is not necessarily true if the print button is placed on the child list applet. If there are no items in the list applet, the print button is disabled, and the end user cannot print from that view. If you only want the end user to print when there are list items, then placing the button on the child list applet is appropriate.

To configure a print button

- 1** From Siebel Tools, add a control to the print applet and specify HTML Type = Button.
- 2** Set Method Invoked = Print.
- 3** Set the Display Name property of the button. Generally, this is set to Print.

Creating Print Templates for the Handheld Application

Once you have identified and created the necessary views, you are ready to create print templates. A print template is a text file that includes instructions for printing a document. It specifies the data to be printed, document layout options, and text formatting. These instructions are specified using a print tagging language that is described in [Appendix E, "Print Tagging Language."](#)

Configuring Business Object Filters in Siebel Handheld

You must configure the Business Object Filters for the Handheld application. These filters affect how data is synchronized between the handheld device and the Siebel database. For information about configuring the default Business Object Filters, see "[Setting Business Object Filters for Siebel Handheld Users](#)" on page 43.

Enabling Signature Capture in Siebel Handheld

You can enable any handheld view to launch and capture signatures from a customer. The views are able to capture multiple signatures from within any view. Signatures are converted to an ASCII text format and stored with the Siebel database as ASCII text. Signatures can also be optionally encoded so as to prevent use of the signature outside of the context in which the signature was captured. The header is configurable allowing you to display any literal value, field value or calculated field value.

The signature field can be configured to show information such as disclaimers and, optionally, the date and time a signature is being captured.

At the bottom of the signature dialog box are 3 buttons. These buttons are described in [Table 7](#):

Table 7. Signature Capture screen buttons

Button	Description
Accept	Tap this button to commit the signature to the database.
Clear	Tap this button to reset and clear the signature field.
Cancel	Tap this button to discard the signature, closet the signature dialog box and return to the view that first invoked the signature dialog box.

Signature Capture Applet Control User Properties

There are 17 customizable applet level user properties that control various elements of signature capture. Most of these user properties are optional except for one user property that is required to pop up the signature dialog. This user property is named, "Signature." Setting this property to "Y" (yes) will enable the signature control to pop the signature dialog.

[Table 8](#) lists the Applet control user properties to control the display of signature control.

Table 8. Signature Capture Applet Control User Properties

User Property	Description
SignatureDataField	Field to save and fetch signature data. NOTE: This field can be a calculated field.
SignatureHeaderField	Field to fetch signature header data. NOTE: This field can be a calculated field.
SignatureFooterField	Field to fetch signature footer data.
SignatureHeaderSaveField	Field to save the signature header data.
SignatureFooterSaveField	Field to save the signature footer data.
MaximumHeaderLines	Maximum number of text lines to display header.
MaximumFooterLines	Maximum number of text lines to display footer.
SignatureHeight	Height of signature capture control. The default value is 80 pixels. Maximum value is 200 pixels.
SignatureDate	"Y" appends a date to the end of the footer.
SignatureTime	"Y" appends a time to the end of a footer and date.
Signature	"Y" enables a signature control for the field.
ShowData	"Y" enables redisplay of signature data.
EncryptKey	Encryption string for storing and reading signatures.

Table 8. Signature Capture Applet Control User Properties

User Property	Description
WritingGuide	Defines appearance of the writing guide within the signature control.
InkColor	Color of the ink used to display signatures.
InkWidth	Width of ink writer.
BorderStyle	Defines border style.

Testing the Siebel Handheld Application

Before deploying your application to your end users, be sure to thoroughly test the application by synchronizing to a handheld device. The handheld configuration is downloaded to the device where you can test the functionality and verify that you have the desired behavior. Another equally important aspect of handheld testing is to check to see how much data is downloaded to the device. If too many records are downloaded, this increases the length of time it takes to synchronize the handheld and slows down the application performance. Check the server log file to see how many records are downloaded for each business component. You must set the LoggingLevels parameter to 25555 to capture this information in the log file.

For more information on the LoggingLevels parameter, see ["Configuring Server Logging Levels" on page 66](#). For more information on the server log files, see ["Direct Server Sync Log Files" on page 133](#) and ["Companion Sync Log Files" on page 134](#).

4

Application Administration

This chapter includes the following topics:

- "Overview of Siebel Handheld Administration Screens" on page 39
- "Setting Up Users in Siebel Handheld" on page 41
- "Assigning User Responsibilities to Siebel Handheld Users" on page 41
- "Administering Siebel Handheld Views" on page 41
- "Setting Business Component Filters for Siebel Handheld Users" on page 42
- "Setting Business Object Filters for Siebel Handheld Users" on page 43
- "Administering Barcode Settings for Siebel Handheld" on page 44
- "About Monitoring Synchronization Sessions for Siebel Handheld" on page 46
- "Monitoring Synchronization Sessions for Siebel Handheld" on page 47
- "Obtaining Error Details from Siebel Handheld Synchronization Sessions" on page 47
- "Obtaining Business Component Information from Siebel Handheld Synchronization Conflicts" on page 48
- "Obtaining an Audit Trail for Siebel Handheld Synchronization Sessions" on page 48
- "Acting Upon Synchronization Errors in Siebel Handheld" on page 48
- "Administering Server Components for Siebel Handheld" on page 49

Overview of Siebel Handheld Administration Screens

You administer Siebel Handheld from a number of administration screens. You access the administration screens from the Site Map on the Siebel Mobile Web Client, and you access the Siebel server from the Siebel Connected Web Client.

The chapter is designed to show you how to administer Siebel Handheld. Key tasks are outlined that you can perform using the Mobile Administration screens. Your organization may follow a different task sequence according to its business requirements.

Following is a list of Administration screens you use when administering your handheld applications. You access these through either the Siebel Mobile Web Client, or through a direct server synchronization.

- **Application Administration:** This screen lists all the handheld applications available within your enterprise. From this view you can create new application settings and administer settings that have already been created. The following views are used by the synchronization engine to extract application definition and user data.

- **Business Component Filters:** This view contains the synchronization filter settings for business components. If you wish to make other business components visible to your users, you change filter settings in this view.
- **Business Object Filters:** This view is where you define data which is downloaded to the Handheld client upon synchronization.
- **Settings:** This view allows you to define parameter settings for your application.
- **Barcode Administration:** This screen allows you to create new barcode definitions for your handheld applications.
- **Barcode Enabling:** This screen allows you to set which views in the Siebel Handheld application are enabled for barcode scanning.
- **Conflict Administration:** This screen allows you access to all data conflict information created by handheld users who synchronize directly to the server. You can take action on particular conflicts and review audit trail information of all conflicts.
 - **Audit Trail:** This view, when enabled, allow you to obtain information about action taken on a particular data conflict.
 - **Business Component Detail:** This setting allows you to see business component information associated with a particular data conflict.
 - **Error Details:** This view allows you to get detailed information about specific data conflicts. You are also able to take particular action about any given conflict.
 - **Field Value:** This view shows the details of a conflict. This provides a more detailed view than the Error Details view.
- **Server Component Administration:** This screen allows you to manage server-level settings for synchronization components. These settings are used by the synchronization engine to extract application definition and user data.
- **Session Administration:** This screen contains a detailed information about user synchronization sessions. Use this view to monitor and investigate handheld user synchronization activities.
- **User Administration:** This screen allows you to manage user-specific settings, such as business object and business components filters, that filter the data that display to the user. The data sets contained in these user screens are used by the synchronization engine to extract application definitions and user data. The Siebel Handheld application is populated by these data when the user performs synchronization.
 - **User Business Component Filters:** This setting contains user-specific sync filter directives for business components.
 - **User Business Object Filters:** These settings contain user-specific queries for business objects. In this setting, you define a data set that is downloaded, at the time of sync, to the Handheld client.
 - **User Settings:** This setting allows you to control user-specific settings which override component and application settings.

Setting Up Users in Siebel Handheld

To set up users on a Siebel Handheld application, perform the following tasks:

- "Assigning User Responsibilities to Siebel Handheld Users" on page 41
- "Administering Siebel Handheld Views" on page 41
- "Setting Business Component Filters for Siebel Handheld Users" on page 42
- "Setting Business Object Filters for Siebel Handheld Users" on page 43

Assigning User Responsibilities to Siebel Handheld Users

You must create user accounts and assign responsibilities and passwords for each handheld user. The steps are the same as those for creating user accounts, assigning responsibilities and passwords for the Siebel Web Client. See *Applications Administration Guide* for more information on this topic.

Administering Siebel Handheld Views

There are two administrative tasks associated with handheld views:

- If you have added a new view or changed the name of a view, you must add the view or update the name of the view in the Application Administration screen.
- Add the default views in the Application Administration screens.

Adding Views to the Handheld Application

You add new views to the Siebel Handheld application from the Application Administration screen in any Siebel Web Client application. You must be logged on as an administrator. (If you are using the Siebel Mobile Web Client to log in as an administrator, you must also specify the `/editseeddata` parameter.)

To add new views to Siebel Handheld

- 1 Launch the Web Client application that uses the same database which the Siebel Handheld application will synchronize to (or will use to synchronize to).

NOTE: If you launch the application from a mobile Web client, specify the `/editseeddata` parameter.
- 2 Choose Navigate > Site Map > Administration-Application > Views.
- 3 Add the new views.
- 4 In the Responsibilities view, associate each view with the appropriate handheld responsibility.

- 5 Add appropriate users to the responsibility.

NOTE: For more detailed instructions on adding views and associating views with responsibilities, see *Applications Administration Guide*.

Specifying Views for the Handheld Application

The Siebel Handheld application uses a small subset of views in the Siebel enterprise application. Because there are memory resource constraints on the handheld devices, it is recommended that you extract only those views that are used on the handheld.

There are two methods for specifying which views are extracted to the handheld. The first method is to compile an .srf of only those views that are relevant to the Siebel Handheld application. Or, alternatively, you may specify the handheld views in Administration-Mobile > Settings view.

The views are specified in the Administration-Mobile > Settings view. By default, all views for the Siebel Handheld application are listed here. Edit the list so that only those views which your application is using appear in the list.

The combination of the .srf file, the specified settings in the Settings view, and the user's responsibility determines which views are extracted. Siebel Server uses the information in the Settings view and the .srf file during synchronization in the following way:

- If no default views are specified, all the views in the .srf are extracted during synchronization. If the .srf contains only the handheld-specific views, then this is the same as listing each handheld view in the handheld configuration file.
- If default views are specified Application-Administration > Settings view, then only those views are extracted. If there are some views that do not match the views in the .srf file, these are ignored.
- If default views are specified in the Application-Administration > Settings view, but *none* of the views match those listed in the .srf file, then all the views in the .srf are extracted.

Setting Business Component Filters for Siebel Handheld Users

The Business Components View in the Application Administration screen contains the sync filter settings for business components. If you wish to add or remove business component filter settings for users, you do so in this view.

To add a business component filter setting

- 1 From the application-level menu, select Navigate > Site Map > Administration-Mobile > Application Administration.
- 2 In the Application Administration screen, select the appropriate application, then click the Business Component view tab.

- 3 Click New, then enter the required information.

Some fields in the Business Component view are described in the following table:

Field	Comments
Owner	A text box. Enter the Handheld application to which the business component will be associated. For example, Siebel <Application name> for CE.
Business Component	A text box. Enter the business component name. For example, Period.
Name	A text box. Enter the business component filter name. For example, Filter 1.
Query	A text box. Enter the syntax for the query. For example, [Start Date] <=Today()

To remove a business component filter setting

- 1 From the application-level menu, select Navigate > Site Map > Administration-Mobile > Application Administration.
- 2 In the Application Administration screen, select the appropriate application, then click the Business Component Filters view tab.
- 3 Select the filter setting record wish to remove.
- 4 From the Business Component Filters menu, choose Delete Record.

Setting Business Object Filters for Siebel Handheld Users

The Business Components View in the Application Administration screen contains the sync filter settings for business objects. If you wish to add or remove business object filter settings for users, you do so in this view.

To add a business object filter setting

- 1 From the application-level menu, select Navigate > Site Map > Administration-Mobile.
- 2 In the Application Administration screen, select the appropriate application, and then click the Business Object Filters view tab.
- 3 Click New, and then enter the required information.

4 The fields in the Business Object Filters view are described in the following table:

Field	Comments
Owner	A text box. Enter the Handheld application to which the business component will be associated. For example, Siebel <Application Name> for CE.
Default	Check the box to allow the filter to work by default.
Business Object	A text box. Enter the business object name. For example, Account.
Name	A text box. Enter the business object filter name. For example, BOFilter 1.
Query	A text box. Enter the syntax for the query. For example, All.

To remove a business object filter setting

- 1 From the application-level menu, select Navigate > Site Map > Administration-Mobile > Application Administration.
- 2 In the Application Administration screen, select the appropriate application, and then click the Business Object Filters view tab.
- 3 Select the filter setting record wish to remove.
- 4 From the Business Object Filters menu, choose Delete Record.

Administering Barcode Settings for Siebel Handheld

By default Siebel Handheld can scan and parse data from HIBC and UCC/EAN barcodes. However, Siebel Administrators can set up Siebel Handheld to scan and parse any 1-dimensional barcode. To do this, Siebel Administrators would need to define the barcodes and how data will be parsed from these barcodes in the Barcode Administration views.

Creating New Barcode Definitions for the Handheld Application

You can define new one-dimensional barcodes in the Barcode Administration views. To define a new barcode, you would need to create a new barcode definition in the Barcode screen, then create corresponding records in the Barcode Item view to define data elements within the barcode.

To create a new barcode definition

- 1 From the application-level menu, select Navigate > Site Map > Administration-Mobile > Barcode Administration.

- 2 Click New, then fill in the fields.

The fields in the Barcodes list are described in the following table:

Field	Comments
Name	Required. Any descriptive name for the barcode. Must be unique for all records defined in the Barcode screen.
Sequence	Required. Order in which to parse a barcode.
Barcode Type	Required. Type of Barcode Standard. Can either be Location or Code. For details on Location and Code barcode types, see "Administering Barcode Settings for Siebel Handheld" on page 44.
Buscomp	Required. Used to designate which business component the target data is be placed into.
Min Length	Used to determine a minimum number, in digits, for data scanned. If data is of a fixed, minimum length is equal to maximum length.
Max Length	Used to determine a maximum number, in digits, for data scanned. If data is of a fixed, maximum length, enter a number which stands for the number of digits.
Prefix	Required. Defines the value that the parsing algorithm will use to identify barcode definition to use.
Suffix	Optional. Allows you to associate suffixes with individual fields.

- 3 In the Barcode Item view, add new records to identify how data will be parsed from barcode. Depending on the type of barcode standard you just defined (either Location or Code), you then need to create new records in the Barcode Item Applet to identify how data will parse into property sets.

- 4 In the Barcode Item applet, Click New, then update the required fields.

Some of the fields are described in the following table:

Field	Comments
Name	Required. Used by algorithm to identify what field to parse this data into (for example Lot Number, corresponds to Lot Number field).
Code	Applicable for Code barcodes only. The number that precedes a data element in a barcode.

Field	Comments
Sequence	Required. For Code barcodes, once code has been matched, this corresponds to sequence used to parse data from barcodes for that data element. For Location barcodes, this corresponds to sequence used to parse data from barcodes.
Min Length	Required. Minimum Length of the character string for this data element. If this is a variable length string, then Minimum Length is not equal to Maximum Length.
Max Length	Required. Maximum Length of the character string for this data element. If this is a variable length string, then Minimum Length is not equal to Maximum Length.
Data Format	Optional. Defines format for data element (for example for date, MMDDYY).

Enabling Applications Views for Barcode Scanning

You can enable any existing or new view for barcode scanning.

To enable an application view for barcode scanning

- 1 From the application-level menu, select **Navigate > Site Map > Administration-Mobile > Barcode Enabling**.
- 2 Click **New**, then enter the necessary information.

The fields in the Barcodes list are described in the following table:

Field	Comments
View	The view in the handheld device from which the scan occurs.
Applet	The applet within the view.
Buscomp	The business component from which the information is be drawn.
Buscomp Field	The specific field within the business component.

About Monitoring Synchronization Sessions for Siebel Handheld

You monitor Handheld application synchronization sessions and synchronization conflicts from a number of screens within the Siebel Mobile Web Client, or if you are using DSS or DSSvP you do so directly on the Siebel server. Every time a user synchronizes with the server, a record is made.

The following topics relate to synchronization monitoring.

- ["Monitoring Synchronization Sessions for Siebel Handheld" on page 47](#)
- ["Obtaining Error Details from Siebel Handheld Synchronization Sessions" on page 47](#)
- ["Obtaining Business Component Information from Siebel Handheld Synchronization Conflicts" on page 48](#)
- ["Obtaining an Audit Trail for Siebel Handheld Synchronization Sessions" on page 48](#)
- ["Acting Upon Synchronization Errors in Siebel Handheld" on page 48](#)

Monitoring Synchronization Sessions for Siebel Handheld

The Session Administration > Sync Status screen allows you to gather all data related to each sync session a user performs. The Sync Status screen contains two views: the Sync Sessions view, and the Extraction Info view. These views allow you to do the following:

- **Sync Status Screen:** Allows you to monitor each user sync session, and includes such data as: sync status, the date, type of sync and so on.
- **Sync Sessions View:** Allows you to gather further information on the status of each sync session, including conflicts during the sync, the size of the data extracted, and so on.
- **Extraction Info View:** Allows you a detailed look at all data extracted during the sync session, including business component information, the number of records extracted, the filters applied and so on.

To monitor synchronization sessions

- From the application-level menu, select **Navigate > Site Map > Administration-Mobile > Session Administration**.

The Sync Status screen appears, with two subordinate views, Sync Sessions and Extraction Info.

Obtaining Error Details from Siebel Handheld Synchronization Sessions

This setting allows you to obtain details of sync errors that occur during individual sync sessions.

To obtain synchronization error details

- 1** From the application-level menu, select **Navigate > Site Map > Administration-Mobile > Conflict Administration**.

The Transactions screen appears.

- 2 In the Transactions screen, select the appropriate record, and then click the Error Details view tab.
- 3 In the Error Details list, select or query for the desired record.

Obtaining Business Component Information from Siebel Handheld Synchronization Conflicts

The Transactions view on the Conflict Administration screen allows you to obtain business component information related to synchronization errors that occur during individual sync sessions.

To obtain business component error details

- 1 From the application-level menu, select Navigate > Site Map > Administration-Mobile > Conflict Administration.
The Transactions screen appears.
- 2 In the Transactions screen, select the appropriate record, and then click the Business Components view tab.

Obtaining an Audit Trail for Siebel Handheld Synchronization Sessions

The Transactions view on the Conflict Administration screen allows you to obtain audit trail information for an action that was taken against a particular transaction.

To obtain synchronization error details

- 1 From the application-level menu, select Navigate > Site Map > Administration-Mobile > Conflict Administration.
The Transactions screen appears.
- 2 In the Transactions screen, select the appropriate record, and then click the Audit view tab.

Acting Upon Synchronization Errors in Siebel Handheld

Upon reviewing a synchronization error, you can act upon it by performing one of three different actions.

To act upon handheld sync transaction errors

- 1 From the application-level menu, select Navigate > Site Map > Administration-Mobile > Conflict Administration.

The Transactions list appears. The transaction buttons are described in the following table:

Action	Result
Reapply	Reapplies the selected transaction with values listed in the view (or Field Value view).
Export	Exports the content of the transaction into a text file.
Ignore	Accepts the current status and does not act upon the error.

- 2 Click either Reapply, Export, or Ignore depending on your needs.

Administering Server Components for Siebel Handheld

You administer server components from the Administration-Mobile > Server Component screen. The component displayed is based on the application selected in the Application Administration view. The Server Component Administration screen is used for overriding application settings at the component level on a specific server. This screen is where you define server level settings, which override settings defined at the application level. The data entered here is used by the synchronization engine when the user synchronizes with the server.

The Server Component screen contains a list of server components associated with the application that was selected in the Application Administration screen. For each server component, the Settings view details the associated settings.

5

Data Filtering

The following topics are covered in this chapter:

- “Developing Data Filters for Handheld” on page 51
- “General and Default Business Object Filters” on page 52
- “Siebel Sales Handheld Business Object Filters” on page 52
- “Recommendation for Managing Handheld Business Object Filters” on page 55
- “Filtering Data for Pick Applets” on page 56

Developing Data Filters for Handheld

The following general steps for are recommended for developing Handheld synchronization filters.

- Identify the screens and views of your application. Then identify the business components that are required to support each screen and view, noting the areas where each business component occurs. For example, identify the form, list, or pick applets that are based on each business component.
- Within Siebel Tools, establish the base parent-child relationships and any reverse relationships at the component level.
- Review the business components that occur in picklists and consider creating default sync filter declarations for those that will cause large numbers of records to synchronize to the device. These declarations are created and maintained in the Mobile Administration screens.
- For each business component, determine whether it is possible to apply a search specification to all instances of the business component within the Siebel Handheld application. Develop a set of suitable Query by Example (QBE) declarations in the Mobile Administration screens. Common examples of business components that are suitable for global QBEs include:
 - Employees (for large organizations)
 - Activities (for example, filter for current Activities, Activities of only certain kinds)
 - Accounts (for example, by geography)
 - Products (for example, active, orderable products)
 - Orders (for example, open, closed in last three months)
- Create appropriate business object synchronization filters for each business object and make sure that each business object includes a default filter. Default filters make sure that users avoid accidental download of an excessive number of records.

General and Default Business Object Filters

There are two types of synchronization filters in Siebel Handheld—general and default filters.

- **General sync filters.** Filters users select to specify the records users want downloaded to their Siebel Handheld application.
- **Default sync filters.** Filters displayed by default the first time the user taps the Select Filters button on the Handheld Sync user interface or if the user synchronizes without first selecting a filter.

There is no naming convention for Siebel Handheld Business Object Filters. The default filter for a business object is indicated by checking the Default flag in the Administration-Mobile > Application Administration > Business Object Filters view.

An asterisk (*) preceding a filter name indicates the filter could be used for sync, if selected, and does not display in the query list in the application. For example, “*No_Accounts.”

General filters appear in the Set Filters dialog when users synchronize their data and, if selected, in the Siebel Handheld application in the Queries drop-down list.

An example of a general filter name is My_Recent_Orders.

Default filters appear in the Set Filters dialog when users synchronize their data and, if selected, in the Siebel Handheld application in the Queries drop-down list. Default filters with the asterisk (*) prefix only appear in the Set Filters dialog; this filter does not show up in the application.

There should only be one default query for each business object. An example of a default filter is Def_Current Activities

CAUTION: Administrators must be sure to define a default filter for each business object in the Siebel Handheld application. If no filters are applied during the synchronization process, an unacceptably high volume of data will be downloaded to the handheld device.

Siebel Sales Handheld Business Object Filters

Table 9 shows the list of filters that come with the Sales Handheld application and the query defined for each filter. All filters are public—that is, they are visible to all end users. You may create additional PDQs or modify the ones that come with the product.

The Sales Handheld application includes all Handheld Business Object Filters for all of the Siebel Handheld applications, some of which are not relevant to Sales Handheld. Therefore, it is recommended that you do a thorough audit of the Business Object Filters and maintain only the ones that apply to your particular business.

NOTE: A default filter must be defined for each screen (or business object) in the application. Only one default filter can be defined per screen or business object.

Table 9. Sales Handheld Business Object Filters

Business Object	Business Object Filter Name	Query Syntax
Account	All_All Accounts	'Account'.Search = "" "'Account'.Sort = "Name, Location""
Account	Def_*No Accounts (Sales)	'Account'.Search = [Id] IS NULL""
Account	Active Accounts	'Account'.Search = "[Account Status] = LookupValue (""ACCOUNT_STATUS"", ""Active"")" "'Account'.Sort = "Name, Location""
Account	CA Accounts	'Account'.Search = "[State] = LookupValue (""STATE_ABBREV"", ""CA"")" "'Account'.Sort = "Name, Location""
Action	All_All Activities	'Action'.Search = "" "'Action'.Sort = "Due""
Action	Def_Uncompleted Activities	'Action'.Search = "[Status] <> LookupValue(""EVENT_STATUS"", ""Done"") OR [Status] IS NULL" "'Action'.Sort = "Due""
Action	*No Activities	'Action'.Search = [Id] IS NULL""
Action	This Week's Activities	'Action'.Search = "[Planned] >= Today() AND [Planned] < Today() + 7" "'Action'.Sort = "Due""
Contact	All_All Contacts	'Contact'.Search = "" "'Contact'.Sort = "Last Name, First Name""
Contact	Def_*No Contacts	'Contact'.Search = [Id] IS NULL""
Contact	CA Contacts	'Contact'.Search = "[State] = LookupValue (""STATE_ABBREV"", ""CA"")" "'Contact'.Sort = "Last Name, First Name""
Employee	All_All Employees	'Employee'.Search = "" "'Employee'.Sort = "Last Name, First Name""
Employee	Def_North American Organization	'Employee'.Search = "EXISTS ([Organization] = ""North American Organization"")" "'Employee'.Sort = "Last Name, First Name""
Employee	*No Employees	'Employee'.Search = [Id] IS NULL""

Table 9. Sales Handheld Business Object Filters

Business Object	Business Object Filter Name	Query Syntax
Employee	All Employees	'Employee'.Search = "" ""Employee'.Sort = "Last Name, First Name""
Expense	All_All Expense Reports	'Expense'.Search = "" ""Expense'.Sort = "Start Date""
Expense	Def_All Expense Reports	'Expense'.Search = "" ""Expense'.Sort = "Start Date""
Expense	*No Expense Reports	"Expense'.Search = [Id] IS NULL""
Expense	In Progress Expense Reports	'Expense'.Search = "[Status] = LookupValue("""EXP_STATUS"" , ""In Progress"") OR [Status] = LookupValue("""EXP_STATUS"" , ""Submitted"")" ""Expense'.Sort = "Submitted Date (DESCENDING)""
Internal Product	All_All Products	'Internal Product'.Search = "" ""Internal Product'.Sort = "Name""
Internal Product	Def_Active Products	'Internal Product'.Search = "[End Date] >= Today() OR [End Date] IS NULL" ""Internal Product'.Sort = "Name""
Internal Product	*No Products	'Internal Product'.Search = [Id] IS NULL""
Internal Product	All Products	'Internal Product'.Search = "" ""Internal Product'.Sort = "Name""
Opportunity	All_All Opportunities	'Opportunity'.Search = "" ""Opportunity'.Sort = "Primary Revenue Amount (DESCENDING), Primary Revenue Close Date (DESCENDING)""
Opportunity	Def_Big Opportunities	'Opportunity'.Search = "[Primary Revenue Amount] > ""500000"" ""Opportunity'.Sort = "Primary Revenue Amount (DESCENDING), Primary Revenue Close Date (DESCENDING)" ""Account'.Sort = "Name, Location""
Opportunity	*No Opportunities	'Opportunity'.Search = [Id] IS NULL""
Opportunity	Current Opportunities	'Opportunity'.Search = "[Primary Revenue Close Date] > Today () - 30" ""Opportunity'.Sort = "Primary Revenue Close Date (DESCENDING)""
Opportunity	New Opportunities	'Opportunity'.Search = "[Row Status] = ""Y"" ""Opportunity'.Sort = "Primary Revenue Amount (DESCENDING), Primary Revenue Close Date (DESCENDING)""
Order Entry (Sales)	All_All Orders	'Order Entry - Orders'.Search = "

Table 9. Sales Handheld Business Object Filters

Business Object	Business Object Filter Name	Query Syntax
Order Entry (Sales)	Def_Open Orders	'Order Entry - Orders'.Search = [Status] <> LookupValue("FS_ORDER_STATUS", "Closed") AND [Status] <> LookupValue("FS_ORDER_STATUS", "Cancelled")
Order Entry (Sales)	*No Orders	'Order Entry - Orders'.Search = [Id] IS NULL
Order Entry (Sales)	All Orders	'Order Entry - Orders'.Search = "
Price List	All_All Price Lists	'Price List'.Search = "" 'Price List'.Sort = "Name"
Price List	Def_Current Price Lists	'Price List'.Search = "[End Date] > Today()" 'Price List'.Sort = "Name"
Price List	*No Price Lists	'Price List'.Search = [Id] IS NULL
Price List	All Price Lists	'Price List'.Search = "" 'Price List'.Sort = "Name"
Quote	All_All Quotes	'Quote'.Search = "
Quote	Def_All Quotes	'Quote'.Search = "
Quote	*No Quotes	'Quote'.Search = [Id] IS NULL
Quote	Active Quotes	'Quote'.Search = [Active] = 'Y' OR [Status] = LookupValue("QUOTE_STATUS", "Active")

Recommendation for Managing Handheld Business Object Filters

The following sections provide recommendations for creating and managing filters with various synchronization methods.

Companion Deployments

Administrators typically provide their users with an initial set of Handheld Business Object filters and instruct them how to manage the synchronization filters themselves later. They are maintained in the Administration-Mobile > Application Administration > Business Object Filters view. This view is hidden from mobile users so they cannot create their own Business Object Filters.

There are several sample Handheld Business Object Filters in the sample database, as well as in the Siebel 7.7 seed data.

Stand-Alone Deployments

For Direct Server Sync deployments, administrators can create user-specific business object and business component filters in the Administration-Mobile > User Administration view. For more information, see ["Setting Business Component Filters for Siebel Handheld Users" on page 42](#) and ["Setting Business Object Filters for Siebel Handheld Users" on page 43](#).

NOTE: These Business Object Filters are made available to all end users and, therefore, must be defined with the needs of all end users in mind.

Filtering Data for Pick Applets

Exercise caution when modifying filter for pick applets, and do so only with the support of a skilled Siebel configurator.

Use default Business Object declarations to force the extraction of data for a given business component in the context of a given Business Object and Visibility type. For more information on visibility designations, see ["Designating Visibility" on page 59](#). The Default Business Object extractions are performed in the first phase of data extraction.

You will most often use these declarations to extract additional data that is not extracted as part of the user interface extraction. This may be useful for business components that are referenced programmatically by other business components, but are not exposed in the user interface. The default business object declarations are used to enforce the extraction of a subset of data to the handheld that would not have been otherwise extracted or, most commonly, to filter the data downloaded for dynamic picklists or pick applets.

All pick data is not downloaded to the device due to the memory constraints on the device. Only pick data for fields that are editable is downloaded. Therefore, if you are doing a query on a pick field, you may not be able to display the picklist. When viewing a record in an applet, if a pick field is read-only, its pick button will be disabled. If end users select a read-only field with a pick control, they receive the following error: "No data available in picklist because field is read-only."

Configuration Directives

These directives are located in the Mobile Administration > Application Administration > Settings view. [Table 10](#) lists the configuration directives that are used to filter data:

Table 10. Configuration Directives

English LOV Display Name	Definition
Allow Remember Password	Enable option for end user to remember username and password.
Batch Download Stagger	Distributes extraction over a period of time.
Batch Initial Download	Sets base time for first poll.
Batch Poll Frequency	Sets polling frequency.
Client Sync Default	Default sync type for sync client.
DB Extract Thread Load	The load (or weight) assigned to each individual Database Extractor thread.
Database Extract Threshold	This is the minimum time the Database Extractor will continue extraction of business components before causing a handshake with the client.
Default BusComp User Props	Defines subset of user props extracted for a business component.
Default Business Object	Amends application definition to include additional business objects including "hidden" and RBOs.
Default Fields	Identifies fields from DefaultBusObj that will be extracted to device.
Default Insert Mode	Sets default for Insert Failure Mode.
Default Pick Mode	Sets default for Extended Pick.
Enable Batch Extraction	Enables Batch Sync.
Enable Sql Trace	Interweaves SQL tracing into handheld sync log file.
Extraction Expiration	Determines valid life span of extract.
Logging Levels	Sets logging levels (must be 5 octal digits).
Max Throttle Wait Time	This is the upper limit on the amount of time any individual throttling request will be allowed to wait.
Max Total Thread Loads	The maximum number of total thread loads that will be allowed to run across the scope defined by Thread Throttle Scope.
No Database BusComp	Define a business component that must be omitted from the device database and excluded from database extraction.

Table 10. Configuration Directives

English LOV Display Name	Definition
No Extract BusComp	Define a business component that must be excluded from database extraction.
Schema Change Notification	Define a Business Service which should receive the Handheld Schema Change Notification.
Thread Throttle Scope	Defines the scope of the thread throttling mechanism.
Transaction Thread Load	The load (or weight) assigned to each individual Transaction Processor thread.
Transaction Threshold	This is the minimum time the Transaction Processor will continue processing transactions before causing a handshake with the client.

CAUTION: Be extremely careful when modifying these declarations. The business objects that are required for internal application functioning differ by application.

Examples of Business Object Declarations

You can set the Default Business Object declarations in the Administration-Mobile > Application Administration > Settings screen, as described in the following examples.

The general format is as follows:

```
DefaultBusObjs22 = Opportunity | 3 | | Account | [Account Status] = "Active" | Action | [Start Date] >= Today () - 30 AND [Start Date] < Today () + 90
```

The example Default Business Object declaration results in an extraction of the Account and Action business components where they occur with visibility "3" using the business object filter indicated. They are not extracted in context of opportunities even though the Opportunity business object was identified. The business object filters are generally used only for extracting business components that do not correspond to any views or applets. Business object declarations identify specific business components within the business object to be extracted. The business object filters normally give a query based on the primary business component in the business object, but do not force extraction of any business components mentioned in the query, therefore, in order for a business component to be extracted from the business object it must be attached to an applet.

Note that there is no business object filter included in the example. A business object filter is only included when you want to force the use of a particular business object synchronization filter. See ["General and Default Business Object Filters" on page 52](#) for more information on business object synchronization filters.

In the following example, the declaration is used to extract all of the Price List Line Items that will display within the Orders screen.

```
DefaultBusObjs13= Order Entry (Sales)|0||Price List Item|
```

Note that this declaration lacks an associated business component statement. When this is the case, all of the records available to the user for the given visibility are extracted.

Another less common way to use the Default Business Object declarations is to set a single Handheld business object synchronization filter for the business objects that are synchronized.

Designating Visibility

It is very important that you use the correct visibility designation in the Default Business Object declarations. The visibility entered should be the visibility that governs the data displayed for the business component within the context of the Business Object specified in the declaration. In the previous Example 1, visibility code 3 is designated. This corresponds to All Visibility, which is the visibility that applies to the Account business component when it is used in a pick applet.

You determine the correct visibility to use by examining View and Business Component properties within Siebel Tools. When creating a Default Business Object declaration to restrict the volume of data extracted for a pick applet, begin by examining the Popup Visibility Type in Business Component Properties. Cross-reference the visibility type to the list below, and enter the appropriate visibility code in the declaration. If the Popup Visibility Type field on the Business Component is null, the default value is All. [Table 11](#) summarizes popup visibility types and the corresponding visibility codes.

Table 11. Visibility Codes

Popup Visibility Type	Visibility Codes
Sales Representative	0
Manager	1
Personal	2
All	3
None	4
Organization	5
Contact	6

NOTE: Do not use the Group, Catalog, or Sub Organization Popup Visibility Types. These are not supported in the CE handheld applications.

Overriding the Popup Visibility

If the Popup Visibility Type setting is not sufficiently restrictive (for example, All visibility), this can lead to a large number of records being extracted when the picklist is processed during synchronization. Making the Popup Visibility Type more restrictive reduces the number of records extracted for picklists. The `OverridePopupVisibility` user property for an applet overrides the Popup Visibility Type on a business component. Use this property when the desired visibility differs from the business component's Popup Visibility Type, and you do not want to change the Popup Visibility Type. If several picklists use the same business component, you can also use the `OverridePopupVisibility` user property to vary the visibility of the picklists in the different applets.

There are two considerations you should keep in mind if multiple applications are sharing the same repository. First, changing the Popup Visibility Type has a global effect for all instances where the business component is used. If multiple applications share the same repository and use the same business components, changing the Popup Visibility Type for a common business component could have an undesirable effect for another application. Second, if multiple applications share the same applet, the picklist in each applet shares the same visibility as defined by `OverridePopupVisibility` property. This is because the `OverridePopupVisibility` property is set on the containing applet.

In Siebel Tools, navigate to Applet > Applet User Properties, and define the `OverridePopupVisibility` user property on the applet containing the control that opens the pick applet. See [Table 12](#) for a description of the syntax. Assign a value to this property using the syntax shown, where `<buscomp field n>` is the underlying business component field of an applet control or column, and `<visibility type>` is the code corresponding to the desired visibility of the picklist's business component. (See [Table 11](#) for a list of the visibility codes.) Because the name of the `OverridePopupVisibility` parameter must be unique, append a unique number to the name of the parameter for any other picklists, for example, `OverridePopupVisibility1`, `OverridePopupVisibility2`, and so on.

Table 12. `OverridePopupVisibility` Syntax

Name	Value
<code>OverridePopupVisibility</code>	<code><buscomp field 1>, <visibility type></code>
<code>OverridePopupVisibility1</code>	<code><buscomp field 2>, <visibility type></code>
<code>OverridePopupVisibility<n></code>	<code><buscomp field n + 1>, <visibility type></code>

NOTE: If `OverridePopupVisibility` is used, then the picklist and pick applet search specifications are ignored during synchronization when the records for the picklist are extracted.

6

Deployment of Siebel Handheld

This chapter includes the following topics:

- "Scripting in the Siebel Handheld Client" on page 61
- "Overview of Server Installation in Support of the Siebel Handheld Client" on page 62
- "Process of Server Installation for Siebel Handheld Direct Server Sync" on page 64
- "About Siebel Handheld Synchronization Performance and Scalability" on page 67
- "Siebel Mobile Web Client Installation" on page 68
- "Process for Installing the Siebel Handheld Application" on page 68
- "Installing Print Templates in the Siebel Handheld Install Directory" on page 72
- "Setting up Siebel Handheld Application Installation on a CompactFlash Card" on page 72
- "Setting the Siebel Handheld Application Restart Parameter" on page 73
- "Changing the SyncURL on Siebel Handheld Devices" on page 73
- "Installing the Siebel Handheld Application from External Media" on page 74
- "Distributing Siebel Handheld Application Patches" on page 74

Scripting in the Siebel Handheld Client

The Siebel Handheld Client does not execute Siebel Visual Basic (VB) or Siebel eScript scripting.

The Siebel Web Client application runs Siebel VB or Siebel eScript scripts and specialized business component logic at synchronization time, rather than in real time on the handheld device. This has significant consequences in applets and controls, because scripts attached to applets and controls are ignored.

Be aware of the following additional issues with respect to scripts and validation:

- **Deactivating scripts.** *Do not* deactivate existing scripts in Siebel Tools to make the handheld device or the synchronization process accept data it is excluding. The script is probably used by the Siebel Web Client, and you can cause damage elsewhere.
- **Calls to user interface methods.** When a business component script makes a call to a user interface method (such as MsgBox), the script cannot be executed, and the record update, deletion, or addition is rejected during synchronization. Strictly speaking, a script attached to a business component should not interact with the user interface, but it is nevertheless a common practice.

Any Siebel Visual Basic code should be restricted to the business component level. Applet-level Siebel Visual Basic will not be executed and, therefore, should not be written for the Siebel Handheld Client application. As a substitute to using Siebel Visual Basic on the Siebel Handheld Client application, for real-time execution, use the following business component user properties:

- BC/Field Read Only Field...for making fields or business components read-only dynamically.
- Pickmap for fields on the picklist.

Do not use message boxes or prompts on the Siebel Visual Basic code used in conjunction with the Siebel Handheld Client application business components. If the business component is shared between the Siebel Handheld Client application and a laptop, use the following construct to determine if the code is being executed in real time on the laptop or during synchronization:

```
'ActiveviewName is only available when the script is called real time on the laptop
If (TheApplication.ActiveviewName<>"") then
MsgBox"....."
End If
```

Overview of Server Installation in Support of the Siebel Handheld Client

This section provides an overview of important factors to consider when planning Direct Server Synchronization (DSS) infrastructure. One aspect of successful planning and execution of a Siebel Handheld DSS deployment is to understand hardware and network requirements. While these factors are generally applicable to all deployments, there are unique aspects to each customer configuration and implementation strategy. Therefore, it is highly recommended that customers conduct detailed configuration, sizing, and production readiness reviews with Siebel Expert Services. This is especially important for complex deployments, such as those supporting large numbers of users over wide geographic areas.

You can also improve the performance and scalability of DSS deployments by working with the Siebel application server component parameters. For more information about the Siebel application server, see ["Optimizing Server Process Management" on page 67](#).

NOTE: The recommendations in this chapter are general ones and are intended to raise your awareness of the key factors in handheld synchronization, performance, and scalability. These factors must be confirmed for your actual environment, and the usage patterns in your enterprise should be taken into consideration.

Server Topology Overview

The diagram in Figure 1 shows the servers and components that are required to deploy Direct Server Sync. The components are the Siebel database, Siebel server, Siebel Web engine, and Siebel Handheld. The synchronization components are the Siebel Sync engine which resides on Siebel server and the Sync client on Siebel Handheld.

CAUTION: Companion Sync uses Siebel Remote to complete the synchronization process to the Siebel server from the laptop. The remote mobile user's routing model must be set to Handheld User. Otherwise, sync will fail. For more information, see *Siebel Remote and Replication Manager Administration Guide*.




Figure 1. DSS Servers and Components

You can improve performance by properly selecting the machine that each server runs on (Web server, Siebel server, database server). For example, increasing the memory and number of spindles improves the database server performance, and increasing the number of CPUs and the amount of memory improves the performance of the application server.

Recommended Hardware and Network Configuration

There are many factors to take into account when designing and implementing your server and network hardware and architecture, and sizing your database. The critical factor in sizing a handheld implementation is the expected peak synchronization load. Specific application variables to consider in calculating this load are: the number of concurrent users, number of transactions, and size of the data file. These variables should be considered within the context of the hardware specifications, including memory and processor speed.

The following resources are available as you plan your Siebel Handheld implementation:

- Refer to Microsoft and manufacturer documentation for comprehensive information on server hardware and registry parameters.
- Refer to Siebel Technical Note 405, *Siebel Handheld Synchronization* for specific recommendations on the following topics:
 - Server Architecture
 - Server Hardware and Registry Parameters

- Database Server Sizing
- Database Tuning
- Dial-Up and Network
- Wireless
- VPN (Virtual Private Networks)
- The Expert Services Handheld Review Package assists customers with planning their hardware and network for handheld implementations. Contact Siebel Expert Services for more information about this program.

Process of Server Installation for Siebel Handheld Direct Server Sync

The server components that are required for Siebel Handheld are installed when you install the Siebel server. See the Siebel Server installation guide for your operating system for details on installing and configuring Siebel server. The Siebel server installer copies the necessary DLLs to create an Object Manager for Direct Server Sync and creates and configures a Server Component and Component Group. The rest of this subsection describes which options you must select to correctly install the software, along with creating or configuring additional Object Managers.

This process includes the following tasks:

- [“Installing the DSS Components Using the Siebel Server Installer” on page 64](#)
- [“Editing the DSS Object Manager Configuration File” on page 65](#)
- [“Configuring Server Logging Levels” on page 66](#)
- [“Optimizing Server Process Management” on page 67](#)

Installing the DSS Components Using the Siebel Server Installer

Install the Siebel server, following the instructions in the Siebel server installation guide for the operating system you are using. When you reach the Setup Type screen in the Installer wizard, you are presented with three installation options:

- **Typical.** This setup option installs all Siebel server components except those displayed.
- **Compact.** This setup option installs only those components necessary to run the Siebel server, but no additional components or help.
- **Custom.** This setup option lets you customize your installation by choosing the specific components you want to install.

To install the Direct Server Sync components with your Siebel Server installation

1 In the Setup Type screen, choose the Custom setting, and then click Next.

NOTE: At this screen, you may also choose a different directory for your Siebel server installation.

2 Choose from the following components:

- Object Manager Component
- Handheld Synchronization
- Siebel Data Quality Connector
- Remote Search Support
- Siebel Java Integrator

The listed Custom Installation options are all selectable.

NOTE: You must enable Handheld Synchronization to enable Direct Server Sync for your DSS installation.

3 Click Next.

Continue with the installation in *Siebel Installation Guide for Microsoft Windows: Servers, Mobile Web Clients, Tools*.

The install wizard automatically installs and configures the DSS components. In addition, the installer creates a configuration file that includes the parameters necessary to properly run the DSS server components and the Business Component filters file.

Editing the DSS Object Manager Configuration File

You must edit the configuration (.cfg) file associated with the DSS server components that you installed and configured to reflect your company's environment.

To edit your configuration file

1 In Windows Explorer, navigate to the directory where the Siebel server is installed and locate the configuration file associated with the DSS server component. By default, this directory is C:\Siebel Root\ siebsrvr\BIN\ENU.

NOTE: By default, the name of the DSS Object Manager configuration file is salesce.cfg, but you can change the name of this file.

2 Create a backup copy of the configuration file and name it salesce.cfg.bak.

This step allows you to recover the original version of the file if you encounter errors.

3 Open the configuration file using a text editor.

- 4 Enter parameter values appropriate for your deployment.

The following table shows the parameters in the .cfg file that may need to be edited to reflect your environment. All other parameters in this section should not require change.

	Parameter	Default Value	Description
[Siebel] section	ApplicationName	SiebelSales for CE	The Siebel Handheld application. This value must match the name of the application as it is specified in Siebel Tools.
	ApplicationTitle	Siebel Sales	The name of the Siebel Handheld application as shown on the Title bar on the browser. This parameter is only used if the Siebel Tools application developed for the handheld is run on the Web client.
	ApplicationSplash Text	Siebel Sales	The Siebel Handheld application name as shown on the splash screen. This parameter is only used if the Siebel Tools application developed for the handheld is run on the Web client.
	ComponentName	Siebel Sales Client	Required for Direct Server Sync, it is entered in the registry on the handheld device.

- 5 Save your changes.
- 6 Restart the component or server.

Configuring Server Logging Levels

To set the logging level, two things need to be done. Logging level must be a number 0-5.

To configure server logging levels

- 1 Log into Server Manager from a (m:\siebel\bin\w32ud) prompt.
- 2 Run the following:

```
change evtloglvl HandheldSyncLog=[LogLevel] for comp [OMName], where [LogLevel] = an integer between 1 - 5 (5 enables all logging) and [OMName] = the OM name (for example, <ApplicationName>CEObjMgr_enu).
```

Optimizing Server Process Management

Several parameters are outlined below that help optimize server processing for Direct Server Sync. To set these parameters, log into a Siebel client as a user with Administrative responsibility and navigate to Servers > Components > Component Parameters through the Screens menu. Select the SalesCE ObjManager (or the appropriate Siebel Handheld application) and update the following parameters to optimize threads per process. For further information and assistance, see Technical Note 405, *Siebel Handheld Synchronization*, and contact Siebel Expert Services about the Siebel Expert Services Handheld Review Package.

- **Max tasks.** This parameter determines the maximum number of threads that can run concurrently for a given component. The value of this parameter should equal the maximum expected peak number of concurrent synchronizations.
- **Min MT servers.** This parameter determines how many multithreaded server processes are started by default for the Siebel Object Manager.
- **Max MT Servers.** This parameter defines the maximum number of processes supported by the instance of the Siebel Object Manager. The value for this parameter should be the same as Min MT servers and should be set so that threads per process (Max Tasks/Max MT Servers) is optimized.

About Siebel Handheld Synchronization Performance and Scalability

There are a number of factors that affect the performance and scalability of handheld synchronization. It is very important that administrators and those involved in the design and deployment of Siebel Handheld understand the impact of usage parameters on synchronization performance and scalability. For more information, see Technical Note 405, *Siebel Handheld Synchronization* for application-specific variables affecting synchronization and data from synchronization scalability tests.

Using Multiple Synchronization Servers

As you scale your deployment, you may need to use multiple synchronization servers to accommodate all of your users. Your end users must be manually assigned to a particular server. Resonate products cannot be used for load balancing. Refer to Technical Note 405, *Siebel Handheld Synchronization* and to your hardware manufacturer's documentation for more information on scaling deployments.

Synchronization Security

The synchronization data stream can be secured using SSL (Secure Sockets Layer).

Siebel Mobile Web Client Installation

You must edit the configuration (.cfg) file associated with syncmanager.exe (the Companion Sync executable) that was installed with the Siebel Mobile Web Client to reflect your user's environment. It may not be practical to individually edit each Companion Sync user's .cfg file; therefore, it is recommended that you create one edited file and distribute it to all your users with Siebel Anywhere. See *Siebel Anywhere Administration Guide* for more information.

Process for Installing the Siebel Handheld Application

Before you deploy the Siebel Handheld application, there are several tasks you need to perform. This process includes the following tasks:

- "Editing the Handheld Application Installation Configuration File" on page 68
- "Enabling Handheld User Database Backup" on page 70
- "Deploying Patches to the Handheld Application with Direct Server Sync" on page 75
- "Deploying Handheld Application Patches with Companion Sync" on page 76
- "Creating Handheld Application Upgrade Kits to Remotely Deploy Patch Files" on page 77
- "Downloading Patches to the Handheld Device" on page 77

Editing the Handheld Application Installation Configuration File

The Siebel Handheld application setup.ini file configures the Siebel Handheld Client application installer. Before you deploy a custom-configured Siebel Handheld application, you must update the parameters in the setup.ini file so that the correct values are written to the device registry before distributing the client installer to end users.

The setup.ini file resides in the Siebel Handheld application directory (for example, the Sales Handheld directory) on the Siebel Handheld DVD-ROM. To modify this file, create a Siebel Handheld installation directory on the network, or create and duplicate a custom DVD-ROM for distribution to end users. This installation directory must include the same files and directory structure as the original DVD-ROM. Then, modify the setup.ini file in the custom installation directory.

NOTE: If you wish to set up parameter values other than default values, add the parameter to the setup.ini file and add the proper values.

Table 13 lists the parameters that you may need to modify in the setup.ini file, their default value, and a description of the parameter.

Table 13. Siebel Handheld setup.ini Parameters

Parameter	Default Value	Description
Version	7.7	Version of the desktop Siebel application against which the Siebel Handheld version synchronizes.
Application Title	Siebel Sales for CE	The Siebel Handheld application. This value must match the name of the application as it is specified in Siebel Tools.
ApplicationName	Siebel Sales for CE	The Siebel Handheld application. This value must match the name of the application as it is specified in Siebel Tools.
ApplicationSplashText	Sales Handheld	The Siebel Handheld application name as shown on the splash screen.
MultiCurrency	True	Required for the application to handle multiple currencies.
SyncURL	<i>http://Web Server Name or IP address/ Virtual Directory Name</i>	Required for Direct Server Sync or Companion Server Sync. This value is entered in the registry on the handheld. See "Changing the SyncURL on Siebel Handheld Devices" on page 73 for more information on this parameter.
[EndUserLocalization] Section		
User DefinedLang	Y	
LogUserDefinedLangErrors	N	
[Printing] Section		See Appendix F, "Print Configuration Settings," for more information on the parameters used to configure printing.
[Backup] Section		Enables handheld database backups. See "Editing the Database Backup Parameters" on page 71 for more information on settings for the parameters in this section of the setup.ini file.
[ApplicationLocation] Section		Specifies where the Siebel Handheld application and database are installed. See "Setting up Siebel Handheld Application Installation on a CompactFlash Card" on page 72 for more information on the parameters in this section of the setup.ini file.

Table 13. Siebel Handheld setup.ini Parameters

Parameter	Default Value	Description
InternetOptionReceiveTimeout	600000	Length of time to receive data (except data extraction) from the server before the handheld client times out. This parameter only applies to synchronizations using Direct Server Sync. In milliseconds. The default value, 600000, is 10 minutes.
InternetOptionSendTimeout	600000	Length of time to send data to the server in a single call the handheld client times out. This parameter only applies to synchronizations using Direct Server Sync. In milliseconds. The default value, 600000, is 10 minutes.
InternetOptionDataExtractionTimeout	900000	Length of time to extract data from the server to the handheld device the handheld client times out. This parameter only applies to synchronizations using Direct Server Sync.
[Logging] Section		
TXNErrorLevel	1	This level controls the extent of transaction error information received from the server
DefaultLogLevel	2	This is for logging messages
MaxLogFileSize	2000	This is for the maximum log file size in KB
MaxSavedLogFiles	3	Determines the number of log files to save.

Enabling Handheld User Database Backup

Siebel Systems provides a way to automatically back up a snapshot of the user’s database and current settings, and to restore those settings in the event of a total device failure. The backup functionality automatically copies all the necessary files to a single compressed file. Each time the user backs up, the backup process creates a new copy of the file and deletes older backups. The backup process must close the application in order to copy the RDBMS and handheld configuration files. After the files are copied, it automatically restarts the application.

The backup feature must be enabled in the application. (For more information on enabling the backup feature, see [“Setting Up Database Backups.”](#)) If the backup feature is enabled, a backup is created during every synchronization. This way, the user retains an up-to-date snapshot of the database, and older backup versions are removed.

When the database backup feature is enabled, a database backup occurs automatically at the end of each synchronization. This makes the overall time to synchronize somewhat longer. The size of the database and the speed of the CompactFlash card also affect the time it takes to complete synchronization.

NOTE: Backups should not be used as a replacement for synchronization.

Setting Up Database Backups

In order to back up the database:

- Provide users with an external memory card.
- Install the Siebel Handheld application with the backup functionality enabled.
- Instruct users to back up their database on a regular basis.

Backing Up to External Media

It is recommended that you back up to external media—for example, a CompactFlash card.

Backing up data to a directory in memory is an option, if external media is not available on the handheld device. However, if the handheld device is damaged, the backup in memory may not be retrievable. Also, when backup data is stored in memory, the amount of memory available to run the application decreases, and application performance may suffer.

Editing the Database Backup Parameters

Before users can back up the database on their handheld devices, you must first enable the Backup menu item on the Siebel Handheld application. This requires editing the setup.ini file to enable backup.

The following is an example of the default settings for the backup parameters:

```
[Backup]
BackupLocation = \Storage Card\Siebel Backup
BackupEnabled = N
```

- BackupEnabled = [Y/N] The default is N (No). Change this setting to Y (Yes) to enable the Backup menu item and to trigger a backup to occur automatically after each synchronization.

If the product is installed with Backup = N, the backup menu item is disabled. You need to change the parameter, then reinstall the product in order to enable the menu item.

- BackupLocation = [Backup location] The default is an external storage card. Specify the location where you want the data backed up. It is recommended that you do not back up to internal RAM because this may have a negative effect on the performance of the application. However, if you back up to RAM, then specify the directory location where you want the data backed up.

For more information on the setup.ini file, see [Chapter 8, "Installing the Handheld Application."](#)

Restoring from a Backup

For information on restoring a database from a backup, see [“Backing Up and Restoring Data with the Siebel Handheld Client”](#) on page 100.

Installing Print Templates in the Siebel Handheld Install Directory

If your application allows printing, you must include all print templates in the template subdirectory of the Siebel Handheld Install directory. The print templates are language-specific, so copy the templates to the template subdirectory within the language directory of the language you are deploying (for example, ...\\ENU\\Template). If the template includes double byte characters, such as Japanese string, you must save the template files as Unicode (UTF16) files. For supported language codes, see *System Requirements and Supported Platforms* on Siebel SupportWeb.

See [Appendix F, “Print Configuration Settings”](#) for more information about Printing.

Setting up Siebel Handheld Application Installation on a CompactFlash Card

The default, when installing Siebel Handheld applications, is to install both the application and the database into RAM on the device. In most instances, there is sufficient available memory, and end users are satisfied with the application performance. There are situations, however, where you may need to optimize the application performance. You can improve performance by installing the Siebel Handheld application on an external storage device.

To improve the performance of the application, it is recommended that you install the application binary files on a CompactFlash card. By doing so, you can free up program memory. Installing the data on the CompactFlash card is not recommended because performance likely degrades.

You can specify, in the application’s setup.ini file, where the application files and database files are to be installed. By default, this is set to the handheld device. In the ApplicationLocation section of the setup.ini file, there are two parameters. The following shows the default settings for these parameters:

```
[ApplicationLocation]
ApplicationBinariesLocation = Device
ApplicationDataLocation    = Device
```

- ApplicationBinariesLocation = Device. The default is Device. To improve application performance, set this to CF (CompactFlash).
- ApplicationDataLocation = Device. The default is Device. It is recommended that you always install the data files on the device.

After you have edited the setup.ini file, follow the instructions for installing the Siebel Handheld application on the client.

Setting the Siebel Handheld Application Restart Parameter

Because of the limited memory on handheld devices, users may find that the performance of the application degrades during the course of a handheld session. This is more likely to occur if the user is making many customer visits and carrying out transactions that involve intensive processing. To minimize the effects of these occurrences, the application can be restarted to release application memory that is not actively being used. The memory that becomes available allows for better performance in the next handheld session.

The application prompts the user to periodically restart the application. A dialog box appears with the message "For optimal application performance it is advised that you Restart your Siebel application by selecting File > Restart." The user can restart the application or ignore the message.

The application prompts the user after a specified number of visits, which is indicated by the number of times the user taps the End Visit button. The frequency with which this message appears is set with the PressureThreshold parameter in the setup.ini file. The default is:

```
PressureThreshold = 29
```

The message is triggered when the user taps the End Visit button $N + 1$ times, where N is the number specified by the parameter. For example, using the default value of 29, the message appears after the 30th time ($29 + 1$) that the user taps the End Visit button.

If the user restarts the application after the message appears, the application resets a counter to 0. If the user ignores the message and does not restart the application, the counter is not reset and, therefore, the message does not reappear.

Changing the SyncURL on Siebel Handheld Devices

Once the Siebel Handheld application is installed, the SyncURL cannot be changed. If you need to change the SyncURL, contact Siebel Technical Support.

Installing the Siebel Handheld Application from External Media

You may create an image of the Handheld Installer that can be loaded onto external media such as a CompactFlash card. When you create a stand-alone installer platform, a Cabinet file (CAB) is created in a location that you specify. The CAB file name should be `siebel.pocketpc_arm.CAB`. You can copy the CAB file to a CompactFlash card, insert the card into the handheld device, and single-click on the file to install the Siebel Handheld application on the device.

NOTE: When installing the application on the device, the end user is asked if he or she wants to install the application in the default directory. Regardless of the user's answer, the application is always installed in the directory specified by the `setup.ini` file. Therefore, the only way to change the directory the application is installed in is to modify the parameters in the `ApplicationLocation` section of the `setup.ini` file.

Creating a Stand-Alone Installer

Users who synchronize in DSS mode may not have a PC, and so may not be able to create a partnership and synchronize using Microsoft ActiveSync. You can install the application for each user through a standard partnership, or you can configure a stand-alone installer as shown in the following pages.

During the installation, the InstallShield Wizard screen prompts you by asking, Would you like to deploy a CAB file to enable rapid installation for additional devices? You can configure a stand-alone installer by selecting Yes.

You are prompted to select a language for the application and to specify a location for the CAB file. The installer creates the CAB file in the location you specify.

The CAB file is a self-extracting file that includes all the files needed to install the Siebel Handheld application on the handheld device. When you single-click the file, the CAB file installs the application.

Distributing Siebel Handheld Application Patches

The Siebel Handheld patch delivery mechanism, PatchAgent, is a tool that automates the deployment of patches to handheld devices as part of the synchronization process. It allows administrators to distribute patches to end users with minimal involvement by the users.

During synchronization the PatchAgent executable is called, and if it detects a handheld patch, it automatically installs the patch on the handheld device. In order for PatchAgent to detect and deploy the patch, the patch files must be created and placed in the directory where PatchAgent expects to find the files.

Deploying Patches to the Handheld Application with Direct Server Sync

In order to set up patch deployment for Direct Server Sync users, you need to patch the Siebel server and patch one handheld client which serves as the “model” from which patch files are pulled. Then the patch files are then packaged and placed in the location on the server where PatchAgent expects to find the files. The next time the end user synchronizes with Siebel server, the patch is installed onto his or her device.

For more information on how the patch process works with synchronization, see [“Downloading Patches to the Handheld Device” on page 77](#).

To set up patch deployment

1 On Siebel server, verify that the following directories exist. If they do not, create the directories.

- C:\patch\AppBinDir
- C:\patch\WinDir

NOTE: You may specify a drive other than C:. However, the directory names must be specified as shown.

- 2** Apply the patch to Siebel server.
- 3** Apply the patch to one handheld client.
- 4** Contact Siebel Technical Support to obtain the list of files to copy from the handheld directory (My Device\Program Files\Siebel Handheld) to the Siebel server directory (C:\patch\AppBinDir).
- 5** Contact Siebel Technical Support to obtain the list of files to copy from the handheld directory (My Device\Windows) to the Siebel server directory (C:\patch\WinDir).
- 6** From the DOS prompt, change directory to *Siebel Root\SWEApp\BIN*.
- 7** Execute the following command to stage the patch files and the patchlist.txt in the correct location on the server:

```
C:\siebel Root\SWEApp\BIN>createpatchlist /s c:\patch /t c:\siebel
Root\sweapp\cepatch
```

/s – source directory. The directory where the patch files were moved.

/t – target directory. The directory where PatchAgent checks for the patch files.

NOTE: You may specify a drive other than C:. However, the location of the source and target directories must be specified exactly as shown.

After the patch files have been moved and the patch list created, the following message appears: “Patch List has been successfully created in *Siebel Root\SWEApp\cepatch* files transferred successfully.”

The patch files are now ready to be deployed to Direct Server Sync end users.

Deploying Handheld Application Patches with Companion Sync

In order to set up patch deployment for Companion Sync users, you need to create a “model” of a patched Siebel Mobile Web Client and a patched handheld client. Then you pull the designated patch files and place them in the correct directory on the end user’s Mobile Web Client. You may use Siebel Anywhere to create upgrade kits to automate this process of distributing patch files to your end user’s Mobile Web Client. The next time the end user uses Companion Sync to synchronize their handheld device with the Siebel Mobile Web Client, the patch is installed on the device.

For more information on how the patch process works with synchronization, see [“Downloading Patches to the Handheld Device” on page 77](#).

To set up patch deployment

- 1 On Siebel server, verify that the following directories exist. If they do not, create the directories.
 - C:\patch\AppBinDir
 - C:\patch\WinDir
- 2 Apply the patch to Siebel server.
- 3 Apply the patch to Siebel Mobile Web Client.

This Mobile Web Client serves as the model from which the patch files can be pulled.
- 4 Apply the patch to one handheld client.

This handheld client serves as the model from which the patch files can be pulled.
- 5 Contact Siebel Technical Support to obtain the list of files to copy from the model handheld directory (My Device\Program Files\Siebel Handheld) to the Siebel server directory (C:\patch\AppBinDir).
- 6 Contact Siebel Technical Support to obtain the list of files to copy from the model handheld directory (My Device\Windows) to the Siebel server directory (C:\patch\WinDir).
- 7 From the DOS prompt, change directory to C:*Siebel Root*\SWEApp\BIN.
- 8 Execute the following command to move the patch files to the correct location and generate a patchlist.txt file:

```
C:\Siebel Root\SWEApp\BIN>createpatchlist /s c:\patch /t c:\Siebel Root\sweapp\cepatch_xxx (where xxx is the language [enu, esn, and so on])
```

/s – source directory. The directory where the patch files were moved.

/t – target directory. The directory where PatchAgent checks for the patch files.

NOTE: You may specify a drive other than C:. However, the location of the source and target directories must be specified exactly as shown.

After the patch files have been moved and the patch list created, the following message appears: “Patch List has been successfully created in *Siebel Root*\SWEApp\cepatch_xxx files transferred successfully.”

- 9 Create the following directory on the end user's Mobile Web Client: *Siebel Root\client\cepatch_xxx* (where xxx is the language [enu, esn, and so on]), and push the files from the *\Siebel Root\SWEApp\cepatch_xxx* directory on Siebel server to the *Siebel Root\client\cepatch_xxx* on the Mobile Web Client.

NOTE: Siebel Anywhere upgrade kits can be used to carry out this step.

Creating Handheld Application Upgrade Kits to Remotely Deploy Patch Files

NOTE: This step is optional. Additionally, you must have a license for Siebel Anywhere to remotely distribute patches to end users.

You may use Siebel Anywhere upgrade kits to remotely distribute self-extracting zip files to your end users' PCs. You can use self-extracting zip files to create new directories and immediately extract files into the directories. Create one upgrade kit for each of the following:

- Create the Siebel Mobile Web Client upgrade kit (Siebel Client Revisions).

Create a single, self-extracting zip file that includes the upgraded .exe and .dll files in the *Siebel Root\client\BIN* directory on the model Mobile Web Client. Contact Siebel Technical Support to obtain the list of files to include. Configure the zip file to self-extract in the *Siebel Root\client\BIN* directory on the end user's Mobile Web Client.

- Create the Siebel Handheld upgrade kit (Siebel Client Revisions).

Create a self-extracting zip file that includes the files in the *Siebel Root\SWEApp\cepatch* directory on the server. Configure the zip file to self-extract in the *\client\cepatch* directory on the end user's Mobile Web Client.

- Create any other upgrade kits as needed (for example, the Siebel Customer Repository File).

Refer to *Siebel Anywhere Administration Guide* for information on creating upgrade kits.

NOTE: If there are read-only files on the Mobile Web Client, the end user may need to change the file attributes to read-write before receiving and installing the upgrade kits. Contact Siebel Technical Support for the list of files whose attributes need to be changed. You may use Siebel Anywhere to distribute a batch script that makes this change.

Downloading Patches to the Handheld Device

Patches are downloaded as part of the synchronization process. Once the patch is staged, the patch is downloaded the next time the end user synchronizes the handheld with Siebel server. The end user synchronizes as he normally would using Direct Server Sync or Companion Sync. First, any transactions are uploaded from the handheld device. Then:

- If a patch needs to be applied to the handheld, the synchronization process terminates, and the patch process is started, which downloads the patch.

- If no patch needs to be applied, the synchronization process continues until the process is complete.

After a successful patch installation, Siebel Handheld Sync will launch automatically and continue the extraction.

If the patch files are not successfully downloaded, the end user is prompted to restart the patch process. The end user must locate and launch patchagent.exe manually. Then, once the patch is successfully installed, the end user is prompted to complete the synchronization.

7

Synchronization Conflict Handling and Recovery with Handheld

This chapter includes the following topics:

- [“Preventing Synchronization Transaction Conflicts with Siebel Handheld” on page 79](#)
- [“Recovering Error Data in Siebel Handheld” on page 84](#)

Preventing Synchronization Transaction Conflicts with Siebel Handheld

When multiple end users synchronize with a remote database, transaction conflicts may occur which can result in data loss. The Extended Pick and Extended Insert functionality minimizes synchronization conflicts. If transaction conflicts are unavoidable, then Siebel Handheld Journaling captures the transaction information so that the data can be recovered. The combination of Extended Pick, Extended Insert, and journaling eliminates the potential for data loss.

There are two features that minimize synchronization transaction conflicts.

- Extended Pick processing
- Extended Insert processing

The next several sections describe these features in detail.

Extended Pick Processing in Siebel Handheld

The handheld is used to capture and record transactions entered by the handheld user. During synchronization, these transactions are processed on the server. A situation may arise in which a transaction fails when it is applied to the Siebel server (through Direct Server Sync) or Siebel Mobile Web Client (through Companion Sync)—both of which are referred to as “server.” For example, a Siebel Handheld user creates a professional call activity for one of his contacts. However, since he last synchronized with the server, the contact involved in this transaction was deleted from the server database. When he tries to synchronize his handheld, the server does not find his contact, and the call activity for the contact cannot be inserted into the server database. To generalize this example, any transaction that involves data selected through picklists or pick applets fails on the server if that pick data is not present at the time of synchronization.

With many handheld users synchronizing with Siebel server and modifying data at different times, this scenario is not uncommon.

The following describes how a pick transaction is recorded on the handheld device and processed on the server during synchronization. Assume that the handheld user wants to create a new call activity for the contact. In order to do this, the user inserts a new record in the Professional Call screen and “picks” the desired contact. When the contact is selected on the handheld, the Row Id of the contact (Contact Id) is recorded. However, on the handheld, the application does not record any of the pick map fields associated with the contact; only the Contact Id is recorded. When the user synchronizes his handheld, that Contact Id is used to locate the contact record in the server database. The Contact Id is then used to retrieve all of the fields used in the pick map for the Contact Id (Last Name, First Name, Middle Initial, Address, City, State, Zip Code, and so on).

In order to minimize pick processing failures, the handheld must record the pick row Id and all of the pick map data that is required for a successful transaction. This data must be recorded at the time of the pick, so that it can be passed to the server for processing. This enhanced functionality is called Extended Pick processing. Now, when the user synchronizes, the transaction is processed on the server as follows:

- The synchronization process first looks for the pick record on the server database. For example, to add an activity it looks for the contact and, if it finds the contact, it retrieves the necessary data and adds the activity. This is the default behavior.
- If the server does not find the pick map record in the database and extended pick processing is enabled, it retrieves the pick record Id and pick map data from the handheld transaction and applies the data directly to the server.

Enabling Extended Pick Processing in Siebel Handheld

You can enable Extended Pick processing through the Application Administration screen in the Mobile Web Client. The parameter is as follows:

DefaultHandheldSyncPickMode

This parameter, when enabled, applies globally throughout the application. When enabled, every handheld pick transaction is subject to pick processing.

To enable extended pick processing

- 1 From the application-level menu, choose Navigate > Site Map > Administration-Mobile > Application Administration.

- 2 Click the Settings view tab, then Query on the following value:

DefaultHandheldSyncPickMode

If there is no such record, a new record with that value should be created. See [Table 14](#) for the values to enter.

Table 14. Business Component User Property Parameters

Business Component User Property	Mode Value	Description
DefaultHandheldSyncPickMode	NoFail	Turns Extended Pick processing ON.
	FailOnError	Turns Extended Pick processing OFF This is the default behavior if the parameter is not specified in the Settings view.

- Business component user property.

The user property is defined on specific business components. The syntax for setting Extended Pick on a business component and the parameter values ([Table 15](#)) follow:

HandheldSyncPickMode=Fieldname|Mode

Table 15. Business Component User Property Parameters

Business Component User Property	Parameter	Value	Description
HandheldSyncPickMode	<i>Fieldname</i>	—	Specify the field name as defined in Siebel Tools.
	<i>Mode</i>	NoFail	Turns Extended Pick processing ON.
		FailOnError	Turns Extended Pick processing OFF.

You may apply Extended Pick processing to multiple fields in a single business component, using the following syntax:

HandheldSyncPickMode=Fieldname1|Mode1, Fieldname2|Mode2

The setting on the business component takes precedence over the setting defined in the Settings view. For example, you can use the business component setting to nullify the global application of Extended Pick. See ["Extended Insert Processing in Siebel Handheld" on page 82](#) for an example. Conversely, you can enable Extended Pick processing on specific business components if the setting in the Settings view has disabled the functionality.

[Table 16](#) shows the combined effect of the settings in the Application-Mobile > Settings View and on a business component.

- The DefaultHandheldSyncPickMode setting is omitted from application settings.

- If there is no setting on a particular business component, the setting defined in the Settings view applies.
- If there is no setting defined in the Settings view, or on the business component, the default behavior is for Extended Pick to be turned OFF.

Table 16. Combined Effect of Extended Pick Settings

Business Component Setting DefaultHandheldSyncPickMode=	Application Settings Value DefaultHandheldSyncPickMode=		
	NoFail	FailOnError	Omitted
NoFail	NoFail	NoFail	NoFail
FailOnError	FailOnError	FailOnError	FailOnError
Omitted	NoFail	FailOnError	FailOnError

Extended Insert Processing in Siebel Handheld

When the server executes an insert transaction and the insert fails, there are two ways the insert failure can be handled:

- A record is logged that indicates the insert failed, and synchronization continues. This is the default insert behavior. The Conflict Administration screen can be used to recover the data.
- The insert failure is logged, including details of the failure, and synchronization is interrupted. This is the extended insert behavior. Extended insert behavior guarantees that, should an insert fail, data loss does not occur since synchronization is stopped until the circumstances causing the failure are resolved.

NOTE: If Extended Insert processing takes place, synchronization is interrupted. The synchronization process continues to fail until the problem is resolved. End users must contact their system administrators to recover from the failure. The recovery effort may involve modifying transactions queued for processing, modifying data on the server, or reentering transactions through the Siebel Handheld application.

Enabling Extended Insert Processing

You can, optionally, have a setting with the following setting name:

DefaultHandheldInsertMode.

This parameter, when enabled, applies globally throughout the application. When enabled, every failed insert interrupts synchronization.

You can enable Extended Insert processing through the Settings view in the Administration-Mobile screen.

Table 17 shows the settings for this parameter.

Table 17. Extended Insert Processing Parameter Setting

Parameter	Mode Value	Description
DefaultHandheldInsertMode	NoFail	Disables Extended Insert processing.
	FailOnError	Enables Extended Insert processing.

- Business component user property.

The user property is defined on specific business components. The setting in the business component takes precedence over the setting defined in the Settings view. Table 18 shows the syntax for setting the Extended Insert on a business component and the parameter values.

HandheldInsertFailMode=*Mode*

Table 18. Business Component User Property Parameter

Business Component User Property	Parameter	Value	Description
HandheldInsertFailMode	<i>Mode</i>	NoFail	Disables Extended Insert processing.
		FailOnErr or	Enables Extended Insert processing.

Table 19 shows the combined effect of the setting in the Settings view and the setting on a business component.

- The business component setting always takes precedence over the settings defined in the Administration-Mobile > Settings view.
- If there is no setting on a particular business component, the Applications Settings value applies.
- If there is no setting in either the Settings view or on the business component, the default behavior is for Extended Insert to be disabled.

Table 19. Combined Effect of Extended Insert Settings

Business Component Setting HandheldInsertFailMode=	Application Settings Value DefaultHandheldInsertMode=		
	NoFail	FailOnError	Omitted
NoFail	NoFail	NoFail	NoFail

Table 19. Combined Effect of Extended Insert Settings

Business Component Setting HandheldInsertFailMode=	Application Settings Value DefaultHandheldInsertMode=		
FailOnError	FailOnError	FailOnError	FailOnError
No Setting on Business Component	NoFail	FailOnError	NoFail

Recovering Error Data in Siebel Handheld

Synchronization errors are captured to the database, and can be accessed through the Conflict Administration screens. This mechanism is always enabled.

To access error data

- 1 From the application-level menu, choose Navigate > Site Map > Administration-Mobile > Conflict Administration.
- 2 Click the Error Details view tab.

8

Installing the Handheld Application

This chapter includes the following topics:

- [“Preparing To Upgrade From a Previous Siebel Handheld Release” on page 85](#)
- [“Installing on the Siebel Handheld Application” on page 85](#)
- [“Reinstalling the Siebel Handheld Application” on page 88](#)
- [“Uninstalling the Siebel Handheld Application” on page 89](#)
- [“Preparing the Siebel Handheld Application for Barcode Scanning” on page 89](#)

Preparing To Upgrade From a Previous Siebel Handheld Release

Siebel Handheld 7.7 does not support upgrades from previous releases of Siebel Handheld applications. To upgrade your existing application and to migrate your data and settings to Siebel 7.7 use the following process.

- Back up the handheld device by synchronizing to your database. See, [“Synchronizing Data on the Siebel Handheld Device” on page 102](#).
- Uninstall your Siebel Handheld application. See, [“Uninstalling the Siebel Handheld Application” on page 89](#).
- Then install the new version of your Siebel Handheld application. See [“Installing on the Siebel Handheld Application” on page 85](#).

Installing on the Siebel Handheld Application

There are two ways to install software onto any Windows-powered handheld device. The first is to create a partnership between a desktop or laptop PC and the handheld device using Microsoft ActiveSync. The second is to install the application from type of external media. See [“Reinstalling the Siebel Handheld Application” on page 88](#) for more information.

NOTE: It is important to remember that end users must synchronize their handheld devices to download the application configuration and populate the database before they can use the application. Therefore, an administrator may install the application for an end user, but the synchronization must occur using the end user’s name and password.

Installing Handheld for Companion Sync Users

Before you install and use Companion Sync (CS) with the Siebel Handheld application, you must first install the Siebel Mobile client on your PC. The Mobile Client Installer copies the Companion Sync files to your personal computer.

NOTE: Users can only use Companion Sync to synchronize their Siebel Handheld application to a personal computer that already has the Siebel Mobile client installed.

To install the Siebel Handheld application and Siebel Handheld Sync using CS

- 1** Using Microsoft ActiveSync, establish a partnership between the handheld device and the personal computer.
- 2** On the PC, network, or DVD, locate the folder where the Siebel Handheld Application folder is installed. In this folder, double-click setup.exe.
- 3** Choose the language you want to use for the installation and click OK.
The Welcome Screen appears.
- 4** Click Next.
The Synchronization Options screen appears.
- 5** Choose the Companion Sync option and click Next.
- 6** Select the desired language of the Siebel Handheld application and click Next.
A window appears showing the setup status, followed by several DOS windows, and the Add/Remove Programs dialog box.
- 7** At the Installing Applications dialog box, click Yes to install in the default directory.
NOTE: The default directory in the Applications dialog is the directory specified by the system administrator in a setup file. So that the application works correctly, the Siebel Installer installs the application in the default directory. Therefore, even if you specify a different location for the application, the application is installed in the default location.
The Siebel Handheld application is installed on the handheld device. During the installation, the Installing Applications dialog box displays a progress bar.
It may take several minutes to install on the handheld device. When the application has been downloaded to the handheld device, the Application Downloading Complete dialog box appears on the PC.
- 8** Click OK.
A message appears informing you that setup has finished installing the Siebel Handheld application on your computer.
- 9** Click Finish.
The Siebel Handheld icon appears in the Start > Programs screen on the handheld device.

After installing the Siebel Handheld application and Siebel Handheld Sync, you must perform an initial synchronization before you can use the application. If you are installing the application for the first time on the device, synchronize the Siebel Remote database with Siebel Server, then synchronize the Siebel Handheld and Siebel Remote databases. See ["Synchronizing Data on the Siebel Handheld Device" on page 102](#) for the procedure for synchronizing your data.

See [Chapter 5, "Data Filtering,"](#) for more information on using Companion Sync and setting filters.

Installing Handheld for Direct Server Sync Users

Most DSS users do not have access to a PC for creating a partnership with their handheld device. In this case, the administrator has to create partnerships with each user's device and install the application. Siebel Handheld applications can be installed in DSS mode using the Siebel Installer as described in this section.

To install the Siebel Handheld application using DSS

- 1** Using Microsoft ActiveSync, establish a partnership between the handheld device and the PC.
- 2** On the PC network or DVD-ROM, locate the folder where the Siebel Handheld Application folder is installed, then double-click setup.exe.

The installation process begins.

- 3** From the Choose Setup Language window, choose the language you want to use for the installation and click OK.
- 4** At the Synchronization Options screen, choose the Direct Server Sync option and then click Next.

The next screen displays and asks, "Would you like to deploy a CAB file to enable rapid installation for additional devices?"

NOTE: If you want to create a stand-alone installer, choose Yes, and then click Next. See ["Reinstalling the Siebel Handheld Application" on page 88](#) for details.

- 5** To install the application on the device, click Next.
- 6** Select the desired language of the Siebel Handheld Application, and click Next.

A window appears showing the setup status, followed by several DOS windows.

- 7 The Add/Remove Programs dialog appears. This is followed by the Installing Applications dialog that asks if you want to install in the default directory. Click Yes to install the Siebel Handheld application on the handheld device.

NOTE: The default directory in the Applications dialog is the directory specified by the system administrator in a setup file. So that the application works correctly, the Siebel Installer installs the application in the default directory. Therefore, even if you specify a different location for the application, the application is installed in the default location.

The Siebel Handheld installation automatically installs SSCE Service Pack 1 and overwrites existing files on your system. A message may appear asking if you want to replace existing files. Respond by tapping "Yes to All."

During the installation, the Installing Applications dialog box displays a progress bar. It may take several minutes to install on the handheld device. When the application has been downloaded to the handheld device, the Application Downloading Complete dialog box displays on the PC.

- 8 Click OK.

A window appears informing you that setup has finished installing the Siebel Handheld application on your computer.

- 9 Click Finish.

The Siebel Handheld and Siebel Handheld Sync icons appear in the Startup screen on the handheld device.

After installing the Siebel Handheld application and Siebel Handheld Sync, you must perform an initial synchronization before the application can be used. Refer to ["Synchronizing Data on the Siebel Handheld Device" on page 102](#) for the procedure for synchronizing your data.

See [Chapter 5, "Data Filtering,"](#) for more information on using Direct Server Sync and setting filters.

Reinstalling the Siebel Handheld Application

Follow the steps below to reinstall or upgrade your Siebel Handheld application.

To reinstall or upgrade the Siebel Handheld application

- 1 Before you reinstall the current application, you must first uninstall the current application on your device. See ["Uninstalling the Siebel Handheld Application" on page 89](#) for more information.
- 2 Once you have uninstalled the application, you may then reinstall the application or install the newer version. See ["Installing on the Siebel Handheld Application" on page 85](#), and follow the instructions for installing the Siebel Handheld application.
- 3 Synchronize your Siebel Handheld application. See ["Synchronizing Data on the Siebel Handheld Device" on page 102](#) and follow the instructions for synchronizing your data.

NOTE: If you are using Companion Sync to synchronize your data, synchronize the Siebel Handheld database with the Siebel Remote database.

Uninstalling the Siebel Handheld Application

Uninstalling the application deletes the database files as well as the application files.

CAUTION: Before you uninstall your application, you must synchronize your database to save any changes to your data since the last synchronization. If you do not synchronize before uninstalling, these changes will be lost. See "Synchronizing Data on the Siebel Handheld Device" on page 102 and follow the instructions for synchronizing your data.

To uninstall the Siebel Handheld application

- 1 Select Start > Settings.
- 2 Select the System tab and tap Remove Programs.
- 3 From Remove Programs, select the Siebel Handheld application and tap Remove.

NOTE: A dialog box appears saying that a file cannot be deleted. This occurs because a file may still reside in memory. Ignore this message and tap OK to delete all application and database files. No additional steps are required to remove the application and database files.

Preparing the Siebel Handheld Application for Barcode Scanning

If you are going to scan barcodes when performing a cycle count, you need to associate the scan trigger with a button on the handheld device.

This assumes that you have already installed the drivers for the scanner you are using with your handheld device. For latest information on supported scanners, please refer to *System Requirements and Supported Platforms* on Siebel SupportWeb.

To associate the scan trigger with a button on the handheld device

- 1 Select Start > Settings.
The Personal Settings tab appears.
- 2 Tap the Buttons Icon.
A table listing the assigned programs is displayed. For example, Button 1 is assigned to Calendar, and so on.
- 3 Select the button to which you want to associate the trigger. For example, Button 1.
- 4 Tap the Button assignment drop-down list.
- 5 Select SocketTrigger from list of programs.

NOTE: You cannot use Button 5 (assigned to Record) as the device button to trigger the scan.

9

Working with Siebel Handheld Applications

This chapter includes the following topics:

- "Components of the Siebel Handheld Interface" on page 91
- "Navigating the Siebel Handheld Interface" on page 94
- "Navigating a List of Records in the Siebel Handheld Application" on page 95
- "Entering Data with the Siebel Handheld Application" on page 96
- "Finding and Querying Data in the Siebel Handheld Application" on page 97
- "Printing with the Siebel Handheld Application" on page 98
- "Exporting Data with the Siebel Handheld Application" on page 98
- "Calendar and Calendar Views in the Siebel Handheld Application" on page 99
- "Setting User Preferences in the Siebel Handheld Application" on page 100
- "Backing Up and Restoring Data with the Siebel Handheld Client" on page 100
- "Synchronizing Data on the Siebel Handheld Device" on page 102
- "Synchronization Troubleshooting with the Siebel Handheld Client" on page 105
- "Improving Siebel Handheld Application Performance" on page 106

Components of the Siebel Handheld Interface

The components of the handheld interface include the Screens menu, Show drop-down list, application-level menu, Queries drop-down list, toolbar, and status bar.

Figure 2 shows the components of the Siebel Handheld application.




Figure 2. Siebel Handheld Screen Components

Screens Menu

The screens menu is the first level of navigation in the Siebel Handheld application. When you launch the Siebel Handheld application for the first time, this tab is labeled Screens unless you have configured a start up view to appear. When you tap the screens menu, a drop-down list of all available screens appears. Tap the desired screen in the list to navigate to it.

For information about configuring a start up view, see ["Setting User Preferences in the Siebel Handheld Application"](#) on page 100.

Show Drop-Down List

The Show drop-down list is the second level of navigation in the Siebel Handheld application. This is where you choose views for the selected screen.

Application-Level Menu

The application-level menu consists of the File, Edit, View, and Help menus. Tap a menu to select a menu option. The options that are available in each menu vary depending on the task you are performing.

Queries Drop-Down List

Up to two predefined queries (PDQs) are displayed in the Queries drop-down list. The list displays the query chosen when you synchronized (or the default filter if you did not change the Set Filters selection) and the All Records query, if it is defined. For more information, see [Chapter 5, "Data Filtering."](#)

Siebel Toolbar

The Siebel toolbar has buttons for frequently used functionality like record navigation and querying. You can configure your toolbar and specify which buttons are displayed. See ["Configuring User Interface Elements in Siebel Handheld" on page 24.](#)

- Tap the New Record button to add a new record to the active list or form.
- Tap the Back button to navigate to the previous view.
- Tap the Forward button to navigate to the view you were in before you selected the Back button.
- Tap the Record Navigation buttons to move through records in a form or a list.
- Tap the New Query button to begin a new query in a form or a list.
- Tap the Execute Query button to run the query you just created.
- Tap the Maximize Minimize Applet button to expand the active applet so that it is the only applet displayed and takes up the entire screen display. This allows you to see more columns or more rows of data at one time. Tap again and the screen displays two applets.

Customizing the Toolbar

You can customize which buttons appear on your toolbar by selecting View > Customize Toolbar from the application menu.

To add and remove buttons from the toolbar, drag and drop the desired buttons between the Choose Toolbar Buttons dialog box and the toolbar.

Minimize Button

The Minimize button appears in the upper right corner of your window. When you tap the Minimize button, the application minimizes, but does not close. To reopen the minimized application, from the Start menu, tap the Siebel Handheld icon. To close (exit) the application, choose File > Exit.

Do not confuse the Minimize button that appears in the upper right corner with the Maximize Minimize Applet button that appears on the Toolbar.

Status Bar

The status bar appears at the bottom of the application window. It provides information about the current view.

Navigating the Siebel Handheld Interface

Navigating the Siebel Handheld application is achieved through the screens menu, the Show drop-down list, drilling down, drilling across, toolbar buttons, and toggling.

Screens Menu

The screens menu provides the first level of navigation. Here you select the screen you want to work in. For more information about the screens menu, see [“Components of the Siebel Handheld Interface” on page 91](#).

Show Drop-Down List

The Show drop-down list is the second level of navigation. After you have selected a screen from the screens menu, select a view from the Show drop-down list. Views in the Show drop-down list are specific to each screen.

For example, in the Activities screen you can pick the My Activities view from the Show drop-down list.

More Info View

To view all of the information available for a record, make sure it is selected, and choose More Info from the Show drop-down list.

NOTE: Not all screens have a More Info view.

Toggling Between Applets

A maximum of two applets can be displayed at one time in a Siebel Handheld application. In situations where there are more than two applets configured and a Toggle button has been configured, you may tap the Toggle button on the applet. Or you may select View > Toggle from the menu to toggle between applets.

Expandable Fields

Due to the limited screen size on the handheld, it is not always easy to view the data in a field without scrolling or resizing the field width. Therefore, some fields that could contain large amounts of text are expandable—that is, the data can be viewed in a text box. An ellipsis (...) appears in the field to indicate that the field is expandable. When you tap the ellipsis, a text box opens showing the data in that field. When you step off the field, the text box closes.

In form applets, an ellipsis is always visible in those fields that are expandable. However, in list applets, due to space constraints, the ellipsis is not always visible in expandable fields. When you tap on an expandable field in a list applet, the ellipsis appears. Once the ellipsis appears, you tap the ellipsis to open the text box.

URLs in Applet Fields

Tapping on a field that contains a URL value launches the URL in Microsoft Internet Explorer.

Navigating a List of Records in the Siebel Handheld Application

Within the view you select from the Show drop-down list, you can view detailed information on a record. When records are displayed in a list, you can drill down or drill across the record to get additional details.

Drilling down occurs when you tap a hyperlink in a record and are taken to another view within the current screen. For example, if you are in the Accounts screen, and tap the Account Name hyperlink, you navigate to the details for that account. You do not leave the Accounts screen; you just move deeper into it.

NOTE: Hyperlinks are indicated by blue underlined text as long as they are set up this way in User Preferences. For more information see ["Setting User Preferences in the Siebel Handheld Application" on page 100.](#)

Drilling across a record occurs when you tap a hyperlink in a record and are taken to another view in a different screen. For example, tapping a hyperlink in the Accounts column of a contact record in the Contacts screen takes you to the record for that account in the Accounts screen.

Dynamic drilldown occurs when you tap a hyperlink in a record and are taken to another screen or just another view. Where you navigate to depends on the content in the drilldown field.

History Arrows

To navigate back to views you have recently displayed, tap the Back button. After you have used the Back button, you can use the Forward button to navigate back to your original screen and view.

NOTE: The History arrows only allow you to navigate between views. These arrows do not allow you to recover data that may have been entered or deleted in another view.

Record Navigation Buttons

Use the Record Navigation buttons to move back and forth through a set of records. The navigation buttons are described in [Table 20.](#)

Table 20. Record Navigation Buttons

Button	Description
	Navigates back to the previous record in the list or form.

Table 20. Record Navigation Buttons

Button	Description
	Navigates forward to the next record in the list or form.
	Navigates back a view based on the navigation history. You can define which views are part of the history. If a view is set to not be recorded as part of the history, the back button won't go back to that view.

Entering Data with the Siebel Handheld Application

There are several different methods for entering data in the Siebel Handheld application. Tap the up arrow next to the Input Panel button to select a method. See the user guide for your device for information on using the different input methods.

Working with Columns in the Handheld Client

Data is displayed in lists and forms in your Siebel Handheld application. You can organize and work within it in a number of ways to better suit your needs.

There are several ways in which to organize columns in a list. You can:

- Sort data by up to three columns
- Resize columns
- Change the order in which the columns appear
- Show and hide columns
- Lock columns for horizontal scrolling

You can sort records in a list by tapping in the column header of the column in which you want to sort the records. If the green column sort indicator points up, the column is sorted in ascending order. If it points down, the column is sorted in descending order.

If you need to sort by more than one column, you can open the Sort Order dialog box to sort up to three columns at one time. Open the Sort Order dialog box by choosing View > Advanced Sort from the application-level menu.

Resize columns by tapping and dragging the divider between the column headings until the column is the desired size.

You can change the order of columns using the Columns Displayed dialog box. Open the Columns Displayed dialog box by choosing View > Columns Displayed.

Show and hide columns using the Columns Displayed dialog box. In the Available columns list, select the items you want to show and tap the arrow to move the selected items to the Selected columns list. To hide columns, select the items and tap the arrow to move the selected items to the Available columns list.

Lock or unlock columns by tapping and holding the column header.

Finding and Querying Data in the Siebel Handheld Application

You can search for data using the Find or Query functionality in your Siebel Handheld application.

About Find in Handheld

Use Find to do a simple search for a record. You can access Find by choosing Edit > Find View > Find... from the application-level menu. This launches the Find dialog box, in which you can enter your search criteria. The asterisk wildcard function (*) can be used in the search criteria. [Figure 3](#) shows an example of the Find dialog window with the following fields: Look In, Last Name, Type, Last Call Date, Primary Specialty, and Rep Specialty.

NOTE: There may be a slight variation in your version of Siebel software, and the Find dialog box may not look exactly as shown here.



Figure 3. Find Dialog Box

About Queries in Handheld

Use Query to locate a number of records containing a specific set of criteria. There are a number of ways in which to perform query tasks in your Siebel Handheld application.

Creating a Query

To begin a query, you can choose Edit > Query > New from the application-level menu, or you can tap the New Query button on the toolbar. Both provide you with a blank form or list where you can enter your query criteria, depending on where you are in the application when you invoke the command. The asterisk wild card function (*) can be used in the search criteria.

Executing a Query

After you have created the query, you can execute it by choosing Edit > Query > Run from the application-level menu or by tapping the Execute Query button in the toolbar.

Refining a Query

You can refine your current query by choosing Edit > Query > Refine from the application-level menu.

Printing with the Siebel Handheld Application

You may print from any view in the Siebel Handheld application that has been configured to support printing. When you print from the handheld, a document that has been configured for the view is printed. You can print directly to a printer, or, if you are not connected to a printer at the time, you can queue your print jobs and wait until you have access to a printer to print your documents.

NOTE: When you print from a view, you are not necessarily printing what is visible on the screen at the time. Every field on the screen may not be relevant for the document. The document may contain only a portion of what is in the view, and it may also contain data that is not viewable at the time. A separate applet, which often cannot be viewed in the user interface, is configured specifically for printing.

The print templates used to generate the printed are installed during the time of setup.

For a list of supported printers, see the system requirements and supported platforms documentation for your application, see *System Requirements and Supported Platforms* on Siebel SupportWeb.

Print from the Siebel Handheld application by choosing File > Print. If you are connected to a printer, the print job runs. If you are not connected to a printer, the print job is sent to a print queue. View the print queue by choosing File > Print Queue.

Exporting Data with the Siebel Handheld Application

You may export data from any view in your application in HTML format or as tab delimited text and save it to a file. This file can be viewed in applications such as Microsoft Pocket Word, Microsoft Pocket Excel, and Internet Explorer.

To export data, select File > Export... to open the Export dialog box.

In the Export dialog box, you may specify the following:

- **Format.** Specify either HTML or Tab delimited text file.
- **Export.** Select Only active applet to export only the data in the active applet. Select All applets in view to export the data in all visible applets.
- **Output file name.** By default, the file is saved in the temp directory with the filename "output." You may tap Browse to specify a different location or filename.
- **Paste Output to Clipboard.** Select the checkbox to save the data to the clipboard.
- **Open file.** Select the checkbox to automatically open the file. When you tap OK in the Export dialog box, the data is exported to the specified file, and the file is automatically opened.

NOTE: You must specify a valid output format for the application. See [Table 21](#) for the correct formats to specify for the supported applications.

Table 21. Export Data Options

To export data to	Do the following
Microsoft Word	Set Format to "Tab delimited text file."
Microsoft Excel	Select the "And paste output to clipboard" check box. The Output format may be set either to HTML or "Tab delimited text file." Paste the data from the clipboard into an Excel spreadsheet.
Microsoft Internet Explorer	Set Format to HTML.

Calendar and Calendar Views in the Siebel Handheld Application

To view your calendar, choose Calendar from the screens menu.

You can view your calendar in a monthly, a weekly, or a daily format. To navigate within the calendar, select the calendar view you want to see from the Show drop-down list.

Customizing the Calendar

You can customize aspects of your calendar from the User Preferences view. For more information, see ["Setting User Preferences in the Siebel Handheld Application" on page 100.](#)

Setting User Preferences in the Siebel Handheld Application

You can customize aspects of your Siebel Handheld application from the User Preferences dialog box. Access the User Preferences dialog box by choosing View > User Preferences from the application-level menu.

In the User Preferences dialog box you can:

- Set a default startup screen.
- Set number of maximum history threads to be saved.
- Set the maximum percentage of the display area that the parent applet can take up.
- Change font size.
- Customize list spacing, column width settings, and grid lines.
- Customize your calendar's default view, start time, time slot interval, and default appointment duration.
- Specify screen aesthetics such as alternating colors for rows and showing drilldown sources as hyperlinks.

Backing Up and Restoring Data with the Siebel Handheld Client

It is recommended that you back up your data to an external device—for example, a CompactFlash card or a Secure ID card. If the handheld device is damaged, the backup may not be retrievable. If you store your backups in RAM, depending on the size of your application and data extract, you may decrease the amount of memory available for the application, and your application performance may suffer.

Automatic Backup After Synchronization

The automatic backup feature must be enabled in the application by your System Administrator. If the backup feature is enabled, a backup is automatically created at the end of every synchronization. This way, you have an up-to-date snapshot of the database. You must never synchronize your data to the handheld device and then restore the database using an older copy of the database. If you do, the next time you synchronize, the application tries to rewrite changed transactions. This can cause data integrity problems. Therefore, when the database backup feature is enabled, a database backup occurs automatically at the end of each synchronization. Keep in mind that this makes the overall time to synchronize somewhat longer. The size of the database and the speed of the CompactFlash card also affect the time it takes to complete synchronization.

Backing Up Data

The following procedure describes how to back up the database on the handheld device.

To back up the database

- 1 From the application-level menu, choose File > Backup.

NOTE: If the Backup menu item is disabled, contact your system administrator to have backup enabled in your application.

A dialog box appears, telling you that backing up the data will restart the application and prompts you to confirm that you want to continue.

- 2 Tap Yes to start the backup.

A status dialog box appears indicating that the backup is in progress and may take a few minutes. The Handheld configuration files and data is copied to the backup location specified in the setup.ini file. Typically, the backup location is a CF or SD card. In some cases, the location is a directory in memory.

A dialog box appears telling you whether the backup succeeded and asks if you want to return to the application.

- 3 Tap Yes to return to the application.

NOTE: If the backup fails, consult your system administrator.

Restoring Data from a Backup

In order to restore the application to its previous state, the user should contact the system administrator. Any work performed on the handheld device since the last backup will be lost.

To restore the database

- 1 Remove the external flash card from the damaged device and place it in a new handheld device where the application has been installed.
- 2 Navigate to the \Program Files\Siebel Handheld folder.
- 3 Start the restore by tapping the BackupUtility file twice.

A dialog box appears, asking you to confirm that you want to restore the device from a previous backup.

- 4 Tap Yes.

A status dialog box appears, indicating that the restore is in progress. The backup utility restores the files to the state when the backup was performed. A dialog box appears telling you if the restore was successful. If successful, it asks you to confirm that you want to restart the Siebel Handheld application.

- 5 Tap Yes to start using the application.

Synchronizing Data on the Siebel Handheld Device

You must synchronize the data on your handheld device:

- After you install or upgrade the Siebel Handheld application.
- Before uninstalling the Siebel Handheld application.
- On a regular basis to keep your data synchronized with Siebel Server and Siebel Mobile Web Client.

The sections that follow describe how to synchronize using Companion Sync (CS), Direct Server Sync (DSS) and Direct Server Sync via Proxy (DSSvP), and provide some troubleshooting tips.

Using Siebel Handheld Synchronization with the Handheld Client

Siebel Handheld Synchronization differs depending on whether users synchronize through Companion Sync or Direct Server Sync. The following procedures show how to launch and use Handheld Synchronization for each method.

NOTE: A given user can only synchronize using one method. For example, it is not possible to install a Siebel Handheld application that a particular user will synchronize both to the Siebel Mobile Web Client database through Companion Sync and also to the Siebel Server database directly through Direct Server Sync.

Using Companion Synchronization with the Handheld Client

End users that synchronize their data using Companion Sync must follow a three-step process to synchronize their handheld, remote, and server databases. Immediately before and after every Siebel Remote sync, you must perform a Companion Sync. This process can be time consuming for the end user and difficult for the administrator to enforce.

Integrated Sync eliminates the need for you to initiate three separate sync sessions for each Siebel Remote sync. Integrated Sync is a one-button process that automatically initiates each of the following synchronization steps:

- 1 Handheld Upload and Processing—Handheld transactions are uploaded to the companion PC and processed.

- 2 Siebel Remote Synchronization—The Siebel Mobile Client is synchronized with Siebel server. Transactions on the mobile client database are uploaded to Siebel server, and changes to Siebel server are downloaded to the mobile client database.

NOTE: If there is a handheld patch staged on the server, synchronization terminates and the patch is installed. After the patch installation is completed, the handheld user is prompted to synchronize again (using either Integrated Sync or Companion Sync) to complete the data extraction and download (that is, Step 3). It is critical that the handheld user synchronize a second time after the patch installation is completed. If he fails to do so, he is not able to start the Siebel Handheld application.

- 3 Handheld Data Extract and Download—Data is extracted from the mobile client database to the handheld device database.

You may use Companion Sync to synchronize your handheld with Siebel Mobile Client as many times as you wish between Integrated Sync sessions. However, it is recommended that you conduct Integrated Sync sessions frequently so that the Siebel Remote synchronization process does not take long periods of time to complete and update conflicts are minimized.

Synchronizing the Handheld Client for Companion Sync Users

When you synchronize, you have the option of either doing an Integrated Sync or Companion Sync. To do an Integrated Sync, select Perform Remote Sync when the Siebel Handheld Sync dialog box appears.

NOTE: You must close your Siebel Handheld application before synchronizing your application.

To perform Companion Sync

- 1 From the companion PC, establish a Microsoft ActiveSync connection to the handheld device.
- 2 From the device, verify that the Siebel Handheld application is closed.

NOTE: On the Pocket PC 2003 operating system, the Minimize button (the button with the "X" in the top right corner of the application) minimizes but does not close the application. To close out the Handheld application in preparation for synchronization, you must use the File > Exit command.

- 3 From the companion PC, choose Start > Programs > Siebel Handheld Sync.

The Siebel Handheld Sync dialog box appears.

- a Enter your user name and password.

- b** By default, Perform Remote Sync is selected. To perform an Integrated Sync, accept the default setting.

If you want to do Companion Sync only, then unselect the Perform Remote Sync box.

Selecting Bypass Set Filters skips the step of selecting the filters and immediately starts the synchronization process. If you select Bypass Set Filters, then the filters that you selected the last time you synchronized are used. If this is the first time you are synchronizing, then the default filters are used.

- 4** Tap Login.

- 5** Tap Set Filters.

The Filters dialog box appears.

- 6** From the Filter list box, select the screen for which you want to choose a filter.

- 7** From the Choose drop-down box, select the filter you want to associate with the screen you selected in Step 6.

NOTE: Tap Default Filters to restore the filter selection to the default setting.

- 8** Tap OK and tap Start to begin synchronization.

- a** The Siebel Handheld Sync dialog box appears. If “Perform Remote Sync” was selected, this is followed by the Siebel Remote dialog box. When synchronization has successfully completed, the Finished dialog box appears.

- b** If a handheld patch needs to be installed, the synchronization process is interrupted and the patch is installed. After the patch is installed, you must restart Siebel Handheld Sync to complete the data extract process. If you fail to do this, you cannot start your application.

- c** The Finished dialog box appears indicating that the synchronization has successfully completed.

- 9** Tap OK to exit Siebel Handheld Sync.

NOTE: If synchronization errors occur, an error dialog box appears.

Using Direct Server Synchronization with the Handheld Client

There are two methods for synchronizing between the handheld device and the Siebel application server:

- Direct Server Sync (DSS) provides synchronization between the Siebel Handheld application and the Siebel application server.
- Direct Server Sync via Proxy (DSSvP) provides synchronization between the Siebel Handheld application and the Siebel application server, using the desktop or companion PC to provide the network connection between the handheld device and the server.

NOTE: You must close your Siebel Handheld application before you synchronize with the Siebel application server.

To synchronize with the Siebel application server

- 1** If you are synchronizing using DSS, create a direct network connection through a modem or a direct LAN connection.

If you are synchronizing using DSSvP, establish an ActiveSync connection between the handheld device and the PC.
- 2** From the device, verify that the Siebel Handheld application is closed.
- 3** From the device, choose Start > Programs > Siebel Handheld Sync.

The Siebel Handheld Sync dialog box appears.
- 4** Enter your user name and password.

Selecting Bypass Set Filters skips the step of selecting the filters and immediately starts the synchronization process. If you select Bypass Set Filters, then the filters that you selected the last time you synchronized are used. If this is the first time you are synchronizing, then the default filters are used.
- 5** Tap Login.

The Siebel Handheld Sync dialog box appears.
- 6** Tap Set Filters.

The Filters dialog box appears.
- 7** From the Filter list box, select the screen for which you want to choose a filter.
- 8** From the Choose drop-down box, select the filter you want to associate with the screen you selected in Step 6.

NOTE: Tap Default Filters to restore the filter selection to the default setting.
- 9** Tap OK, and then tap Start to begin synchronization.

NOTE: If a handheld patch needs to be installed, the synchronization process is interrupted and the patch is installed. After the patch is installed, you must restart Siebel Handheld Sync to complete the data extract process. If you fail to do this, you cannot start your application.

The Finished dialog box appears indicating the synchronization has successfully completed.
- 10** Tap OK to exit Siebel Handheld Sync.

NOTE: If synchronization errors occur, an error dialog box appears.

Synchronization Troubleshooting with the Siebel Handheld Client

This section lists potential error messages that are associated with synchronization. In addition, this section explains how to fix transaction errors.

General Synchronization Errors

There are a number of different errors that can occur when synchronization does not complete successfully, for example:

- Faulty wire connection
- Server crash
- Insufficient memory
- Login error

When these errors occur, the user should exit Siebel Handheld Sync and launch the application again.

NOTE: When you restart Siebel Handheld Sync, you may see an error message that says that another instance of `syncmanager.exe` is running. You are asked whether you want to terminate the first instance or not, and you should choose Yes.

Transaction Conflicts

Transaction conflicts are minimized when customers adhere to the standard configuration practices outlined in this document. However, even when proper configuration practices are followed, conflicts can occur for a variety of reasons. For example, if a field value is updated on both the handheld client and the server between synchronization events, a transaction update conflict occurs. In this instance, the user is presented with an error dialog after synchronization has completed.

A transaction consists of one or more smaller transactions called mini-transactions. For example, if you update several fields in a record, the update to the record counts as a single transaction, and each update to a field is a mini-transaction. The Siebel Handheld application behaves in the same way as the Siebel Web application in that if any part of the transaction fails, the entire transaction fails. Assume, for example, that you update four fields in a record. If, during synchronization, three fields update correctly and one field fails to be updated, none of the fields in the record is updated.

Improving Siebel Handheld Application Performance

If you find that the performance of the Siebel Handheld application is very slow or begins to degrade, the following can help to improve the application performance:

- Verify that your device meets the minimum memory requirements. See *System Requirements and Supported Platforms* on Siebel SupportWeb.
- When you run the Siebel Handheld application, it is recommended that you do not run any other applications. By doing so, you maximize the amount of memory that is available to run the application.
- Increase the amount of memory that is allocated for running applications.
- Installing the binaries to a CompactFlash card. For more information, see "[Setting up Siebel Handheld Application Installation on a CompactFlash Card](#)" on page 72.

To increase application memory

- 1** From the Start menu, select Settings.
- 2** Select the System tab and tap Memory.
- 3** Move the slider bar so that more memory is allocated to Program Memory, then tap OK.

10 Using Siebel Sales Handheld

This chapter includes the following topics:

- [“About Using Siebel Sales Handheld” on page 109](#)
- [“About Managing Contacts in Siebel Sales Handheld” on page 109](#)
- [“Managing Accounts in Siebel Sales Handheld” on page 111](#)
- [“Developing Opportunities in Siebel Sales Handheld” on page 114](#)
- [“Managing Customer Relationships in Siebel Sales Handheld” on page 118](#)
- [“Developing Quotes in Siebel Sales Handheld” on page 122](#)
- [“Managing Orders in Siebel Sales Handheld” on page 126](#)
- [“Tracking Expenses in Sales Handheld” on page 128](#)

About Using Siebel Sales Handheld

Siebel Sales Handheld provides mobile sales professionals with the sales tools and information to manage sales processes such as opportunity, account and contact management while they are in the field or away from their desk.

Although the sales process varies by organization, certain similarities do exist. Siebel Sales Handheld has been designed so that each organization can adapt its usage to best suit mobile business needs while building on similarities in practices found across many sales organizations. Organizations can use Siebel Sales Handheld in conjunction with the Siebel Sales Web client application or as a stand-alone product.

Sales representatives may use the handheld to record contact and account information, manage opportunities, schedule sales activities, check product and pricing information, provide quotes and orders, and create expense reports. In addition, sales administrators and sales managers can customize the software to fit current business needs.

About Managing Contacts in Siebel Sales Handheld

Contacts are individuals with whom your company conducts business or expects to conduct business in the future. Contacts can be employees of other companies, independent consultants, vendors, or personal acquaintances. Contacts may be associated with several accounts, but a contact may be primary on only one account. Contacts may be associated with a number of opportunities, including those that are not related to their accounts.

The following contact management topics are included in this section:

- [“Scenario for Managing Contacts in Sales Handheld” on page 110](#)
- [“Adding Contacts in Sales Handheld” on page 110](#)
- [“Associating Contacts with Opportunities in Sales Handheld” on page 111](#)

Scenario for Managing Contacts in Sales Handheld

At a trade show, a sales representative exchanges business cards with the people she meets. Instead of waiting until she returns to her office, the sales representative uses Siebel Sales Handheld to enter essential contact information. When she returns to her office, she identifies individuals that may be possible sources for leads.

As the sales representative works with each contact, the possibility of doing business—an opportunity—may arise. If so, she can then create an opportunity and associate contacts and activities with it to track important milestones and key players for closing the deal.

Adding Contacts in Sales Handheld

Use the My Contacts or Personal Contacts views to enter information about your contacts. Contacts entered using the Personal Contacts view are not shared with team members.

To add a contact

- 1** Navigate to the Contacts screen.
- 2** From the Show drop-down list, select My Contacts, or Personal Contacts.
 - My Contacts: Use this list for contacts that you might or might not share with the rest of your organization.
 - Personal Contacts: Use this list for contacts that are not shared with the rest of your organization.
- 3** Tap the New Record button, then fill the Last Name and First Name fields.
- 4** From the Show drop-down list, choose More Info, and then complete additional fields, as needed.

The following table describes some fields in the Contact form.

Fields	Comments
Job Title	A text field that displays the Contact’s professional title.
Account	Displays the primary account with which the contact is associated. A contact may be associated with more than one account, but may be the primary contact on only one account at a time. To associate the Contact with an Account, navigate to the Contacts > Accounts view (if configured).

Fields	Comments
Work Phone Number	A text field that displays the contact's work telephone number.
Site	A default value that populates automatically based on the location of the primary account.

Associating Contacts with Opportunities in Sales Handheld

A contact may be a source of revenue for your company. Potential revenue-generating events are called Opportunities. You will want to associate a contact with an existing opportunity to track information about both the opportunity and the contact. For more information, see ["About Creating Opportunities in Sales Handheld" on page 115](#).

To associate a contact with an existing opportunity

- 1** Navigate to the Contacts screen.
The My Contacts list appears.
- 2** In the My Contacts list, select the contact with whom the opportunity will be associated.
- 3** From the Show drop-down list, choose Opportunities.
- 4** Tap in the Opportunities list, and then tap the New Record button.
The Add Opportunities list appears.
- 5** In the Add Opportunities list, select the opportunity to associate with the contact, and then tap OK.

Managing Accounts in Siebel Sales Handheld

An account represents the relationship between your company and the companies or individuals with whom you do business. You use the Accounts screen and its associated views as the primary navigation tool for your customer interactions.

The following topics related to account and account management are included in this section:

- ["Scenario for Managing Accounts in Sales Handheld" on page 112](#)
- ["Creating Accounts in Sales Handheld" on page 112](#)
- ["Associating Activities with Accounts in Sales Handheld" on page 113](#)
- ["Associating Opportunities with Accounts in Sales Handheld" on page 114](#)

Scenario for Managing Accounts in Sales Handheld

A prospect is interested in learning more about the products and services that your company sells. The sales representative sets up a time for a sales call later in the week.

During the sales call, the sales representative asks a number of questions to determine the account structure of the prospect's business to help the representative determine how best to fit the prospect's product needs. The sales representative learns that the prospect's business has a total of four locations, and that sales and service are billed through the main office, although each location receives a billing statement.

After the sales representative meets with the prospect, he creates the account structure for his business.

Creating Accounts in Sales Handheld

When you identify a possible lead, the lead can be added as an account. You can then begin to add and track information about the account.

To create an account

- 1 Navigate to the Accounts screen.
The My Accounts list appears.
- 2 Tap the New Record button.
- 3 In the Name field tap the ellipsis (...), enter a name for the account, and then select More Info.
- 4 In the More Info view, complete the necessary fields.

To add account addresses

- 1 Navigate to the Accounts screen.
The My Accounts list appears.
- 2 Select the account record, and from the Show drop-down list, choose Addresses.
- 3 In the Account Addresses view, tap the Addresses list to select it, and then tap the New Record button.
- 4 Complete the fields for the address, and tap the Primary field to display a check mark if this is the primary address for the account.

To add additional account information

- 1 Navigate to the Accounts screen.
The My Accounts list appears.
- 2 From the Show drop-down list, select More Info.

3 Complete the fields to add additional information.

The following table describes some fields in the More Info form. The name and address fields are automatically populated with information entered at the My Accounts and Addresses views.

Fields	Comments
Parent Account	Select the parent account from the Pick Account picklist.
Account Type	Pick the Account Type from the list. Examples are Fulfillment Shipper, Commercial, Competitor.
Account Team	Displays the primary Account Team member with which the account is associated. To associate the account with one or more team members, navigate to the Account > Account Team view.
URL	Text entry.
Industries	Displays the primary industry with which the account is associated.
Price List	Choose applicable price list from the Pick Price List dialog box.
Current Volume	Enter amount, or tap the ellipses and enter Currency Code, Exchange Date and Amount in the dialog box. Then tap OK.
Potential Volume	Enter amount, or tap the ellipses and enter Currency Code, Exchange Date and Amount in the dialog box. Then tap OK.
Status	A list of values established by your company. Status examples might be Qualified, Silver, Active.
Currency	Select the currency code from the Pick Currency Code list.

The My Accounts list appears.

Associating Activities with Accounts in Sales Handheld

An activity is a task or event that is generally, but not always, performed for a contact, account, or opportunity. You will likely have many meetings, calls, presentations, and other activities surrounding an account.

Activities provide a place to enter and track this information. If the activity entered has a time associated with it, it will appear on the Activities and Calendar screens.

To associate activities with accounts

1 Navigate to the Accounts screen.

The My Accounts list appears.

2 In the My Accounts list, select the account with which the activity will be associated.

3 From the Show drop-down list, select Activities.

- 4 In the Account Activities view, tap the Activities list to select it, and then tap the New Record button.
- 5 In the new row, complete the necessary fields.
The Type field defaults to Appointment.
- 6 Drill down on the default activity Type hyperlink to display the Activities screen's More Info view.
- 7 In the More Info form, add and edit details about the activity.
For more information, see ["Creating Activities in Sales Handheld" on page 119](#).

Associating Opportunities with Accounts in Sales Handheld

Accounts are a source of business for your company. An opportunity is a potential revenue-generating event and is another type of information that you can use to manage your accounts within Siebel Sales Handheld.

To add an opportunity to an account

- 1 Navigate to the Accounts screen.
The My Accounts list appears.
- 2 From the Show drop-down list, select My Accounts.
- 3 In the My Accounts list, select the account to which the opportunity will be associated.
- 4 From the Show drop-down list, choose Opportunities.
The Account Opportunities view appears.
- 5 In the Account Opportunities view, tap the Opportunities list to select it, and then tap the New Record button.
- 6 In the Opportunities list, complete the necessary fields for the new record.
The Account field is automatically populated with the name of the selected account. Sales stage selections are based on the sales methods used by your organization.

Developing Opportunities in Siebel Sales Handheld

An opportunity is defined as a potential revenue-generating event. An opportunity is usually associated with an account and one or more contacts, products, activities, and quotes.

Examples of opportunities are:

- At a trade show, a company representative expresses interest in purchasing a product.

- When called by a telesales representative, a contact indicates interest in contracting maintenance services.
- In a conversation with an existing client, the client expresses an interest in upgrading to the newest product model.

The following topics related to opportunities are included in this section:

- ["Scenario for Developing Opportunities in Sales Handheld" on page 115](#)
- ["About Creating Opportunities in Sales Handheld" on page 115](#)
- ["About Sales Methods in Sales Handheld" on page 116](#)
- ["Associating a Contact with an Opportunity in Sales Handheld" on page 117](#)
- ["Associating a Product with an Opportunity in Sales Handheld" on page 117](#)
- ["About Opportunity Quotes in Sales Handheld" on page 118](#)

Scenario for Developing Opportunities in Sales Handheld

A sales representative is involved in revenue-generating and customer contact activities at her company. At a trade show she meets a prospective customer who could be a lead for a new business opportunity. Using her Siebel Sales Handheld application, the sales representative discovers that the company is listed in Siebel Sales as an account, but the person she met is not listed as a contact associated with the account.

After adding this person as a contact, the sales representative creates the opportunity. Next, the sales representative schedules meetings, records the associated activities, and associates other important contacts to the opportunity.

As the sales process continues, the sales representative gathers and updates information about the account, its contacts, and the opportunity. As the relationship grows, the sales representative can add, view, and share information and key knowledge with other members of the sales team.

About Creating Opportunities in Sales Handheld

Each time you identify an opportunity, you should create a new record.

To create an opportunity

- 1 Navigate to the Opportunities screen.
The My Opportunities list appears.
- 2 Tap the New Record button, and enter a name in the Name field.

- 3 From the Show drop-down list, choose More Info and complete additional fields.

The following table describes some fields in the Opportunities - More Info form.

Field	Comments
Name	A required value that identifies the opportunity.
Account	Allows you to associate an opportunity with an account.
Description	A text area for additional information about the opportunity.
Site	A default value that populates automatically when you associate the opportunity to a specific account and location.
Primary	Displays the primary Sales Team member for the opportunity. To associate the opportunity with one or more team members, navigate to the Opportunity > Sales Team view (if configured).
Rev:	Revenue. Allows you to enter the currency amount of the opportunity. This field defaults to zero.
Probability %	Allows you to enter the percentage of confidence you have that the deal will close with the specified revenue on the specified close date. Probability automatically updates based on the Sales Method and Sales Stage selected.
Expected Value	Displays a currency value that is calculated based on the potential revenue field multiplied by the value in the probability field. A lower percent in the probability field reduces the expected value that will be included in your revenue forecast.
Close Date	A required field that allows you to enter the expected date on which the opportunity will close. The default date is the same as the Created Date. It is important to modify the date, if the opportunity will close on a different date, since this date is used in revenue forecasting.
Lead Quality	A list of values established by your company that allows you to rank the quality of the lead. Default values include 1-Excellent, 2-Very High, 3-High, 4-Fair, 5-Poor.
Sales Method	A list of values established by your company that list the sales methodologies. For more information, see "About Sales Methods in Sales Handheld" on page 116 .
Sales Stage	A list of values established by your company that lists the sales stages associated with the sales method you selected.

About Sales Methods in Sales Handheld

A sales method is a formalized approach or methodology used during the sales process. A sales method can encompass all activities associated with the sales process, from prospecting to forecasting to closing deals. This approach allows sales representatives to use the most appropriate method for opportunities.

The application administrator will create and implement the sales stages your company uses, and then establish values in your Siebel application that represent these methods and stages. A recommended business practice is to designate a default sales method in your Siebel application. This practice allows a sales method to be associated with each opportunity and aids in charting and reporting accuracy.

Sales methods can differ within a company. For instance, a sales method for managing a complex multimillion dollar opportunity may include 15 stages, while a sales method for a simple low-dollar opportunity may require only four stages.

For more information about creating or implementing sales stages, see *Applications Administration Guide*.

Associating a Contact with an Opportunity in Sales Handheld

As you work with an opportunity, you will want to maintain information about the contacts associated with the opportunity. For more information about contacts, see [“Adding Contacts in Sales Handheld” on page 110](#).

The Opportunities screen’s Contacts view allows you to associate and review contact-related information for an opportunity.

To associate a contact with an opportunity

- 1** Navigate to the Opportunities screen
The My Opportunities list appears.
- 2** In the My Opportunities list, select the opportunity with which you will associate a contact.
- 3** From the Show drop-down list, choose Contacts.
- 4** Tap the Contacts list to select it, and then tap the New Record button.
- 5** In the Add Contacts dialog box, select the contact or contacts you wish to add, and then tap OK.

NOTE: To select multiple records, tap the control key and select the contact records.

Associating a Product with an Opportunity in Sales Handheld

Specific products can be associated with an opportunity. For example, if a customer is interested in purchasing a new product model, this information can be entered in the Products view.

After the information is entered, you can drill down on the product to find additional information such as product features and prices.

To associate a product with an opportunity

- 1** Navigate to the Opportunities screen.
The My Opportunities list appears.
- 2** In the My Opportunities list, select the opportunity with which a product will be associated.
- 3** From the Show drop-down list, choose Products.
- 4** In the Opportunity Products view, tap the Products list to select it, and then tap the New Record button.
- 5** In the new row, tap the arrow in the Products field.
- 6** In the Pick Product dialog box, select the product, and then tap OK.
- 7** Complete the remaining fields, as needed.

About Opportunity Quotes in Sales Handheld

The Opportunity Quotes view displays quotes that have been generated for a specific opportunity. After adding products to an opportunity in the Opportunity Products view, you can navigate to the Opportunity Quotes view to initiate Auto Quote functionality or to manually create a quote. For more information, see ["Creating Quotes in Sales Handheld" on page 122](#).

Managing Customer Relationships in Siebel Sales Handheld

An organization's records should accurately reflect the amount of work required and performed to maintain customer satisfaction. This practice avoids duplication of effort if a different or an additional team member has to get involved. It also keeps everyone up to date as to exactly what activities have occurred and when they have occurred.

The following topics related to Activities are included in this section:

- ["About Activities in Sales Handheld" on page 119](#)
- ["Scenario for Managing Activities in Sales Handheld" on page 119](#)
- ["Creating Activities in Sales Handheld" on page 119](#)
- ["Delegating Activities in Sales Handheld" on page 119](#)
- ["Associating Contacts with Activities in Sales Handheld" on page 120](#)
- ["Adding General Activities Using the Calendar in Sales Handheld" on page 120](#)

About Activities in Sales Handheld

Activities are various tasks or events that are performed for contacts, accounts, and opportunities. Activities that are given start times are automatically entered on the activities screen and your calendar.

Scenario for Managing Activities in Sales Handheld

While working away from his desk, a sales manager receives a call from a customer who wants to visit the sales manager's company for an executive summary meeting. The customer also wants the sales team to perform a product demonstration. The sales manager schedules the meeting using his handheld. After his next synchronization, the meeting appears on calendars of his team members. The sales manager delegates the tasks required to prepare for the meeting, such as preparing presentation slides, reserving a conference room, and configuring the demo system. These activities appear in the sales manager's Activities screen and calendar for the customer's account.

As the sales manager and his team members complete the activities, the activities are marked as done, providing key status information about the opportunity.

Creating Activities in Sales Handheld

Throughout the day, you have new tasks to accomplish and activities to monitor. These activities are part of your business. By keeping track of these activity records on your handheld, you make sure your team members know about these tasks, and you create a valuable history of your past interactions with customers.

To create a new activity

- 1** Navigate to the Activities screen.
The My Activities list appears.
- 2** Tap the New Record button, and in the new row, complete the necessary fields.
A default value is provided in the activity Type field.
- 3** Drill down on the hyperlink value in the Type field.
- 4** In the More Info form, pick the appropriate activity type from the list, and complete the fields.

Delegating Activities in Sales Handheld

If you work as part of a sales team or are the manager, an important part of managing your activities includes managing other people's activities. When an activity needs to be performed by someone else, you can reassign or delegate it to an employee.

To delegate an activity

- 1** Navigate to the Activities screen.
The My Activities list appears.
- 2** In the My Activities list, find the activity that needs to be delegated.
- 3** From the Show drop-down list, select Employees.
- 4** In the Activity Employees view, tap the Employees list to select it, and then tap the New Record button.
- 5** In the Add Employees list, select the employees to whom the activity will be assigned.
- 6** To make an employee the primary for the activity, tap the Primary field to display a check mark.

Associating Contacts with Activities in Sales Handheld

When you add an activity to your calendar, you may also want to have a record of contacts who will be participating in the activity.

To associate contacts with activities

- 1** Navigate to the Activities screen.
The My Activities list appears.
- 2** In the My Activities list, select the activity with which a contact will be associated.
- 3** From the Show drop-down list, select Contacts.
- 4** In the Activity Contacts view, tap the Contacts list to select it, and then tap the New Record button.
- 5** In the Add Contacts dialog box, select the contacts, and then tap OK.

Adding General Activities Using the Calendar in Sales Handheld

General activities and appointments must have the Planned Start and Duration fields populated in order to be displayed in the correct time slot on the Daily Calendar view.

To add a general activity in the Calendar view

- 1** Navigate to the Calendar screen.
- 2** From the Show drop-down list, select Daily, Weekly, or Monthly.
- 3** For My Weekly or My Monthly, select the day on which you want to schedule a general activity.

- 4 On the toolbar, tap the New Record button.
You may also tap an open time slot within the daily view.
- 5 In the new record, complete the necessary fields for the appointment or task.
Some fields are described in the following table.

Field	Comments
Type	The type of activity. Activity types might be call, email-outbound, demonstration, and so on.
Planned Start	This date-time field defaults to the time selected when you created the new appointment.
Duration	When the duration is updated, the planned completion time is automatically adjusted.
Account	Complete this field if the activity is related to a particular account.
Repeat	Tap the check box to display a check mark if the appointment or task is recurring. Siebel Handheld Calendar does not support modification of single instances of recurring activities. For example, if you delete or modify an appointment scheduled to recur daily for 10 days, the entire series will be deleted.
Repeat Until	The end date of a repeating appointment.

To specify contact participants

- 1 Navigate to the Calendar screen and locate the day the task or appointment occurs.
- 2 Drill down on the task or appointment hyperlink to display the Calendar form.
- 3 From the Show drop-down list, select Contact Participants.
- 4 In the Calendar Contacts view, tap the Contacts list to select it, and then tap the New Record button.
- 5 In the Add Contacts dialog box, select contacts and tap OK.

To specify employee participants

- 1 Navigate to the Calendar screen and locate the day the task or appointment occurs.
- 2 Drill down on the task or appointment hyperlink to display the Calendar form.

If the appointment or task repeats over time, you will be asked to indicate if changes to the appointment should be applied to the specific occurrence, or to all occurrences. From the Show drop-down list, select Employee Participants.
- 3 From the Show drop-down list, select Employee Participants.
- 4 In the Calendar Employees view, tap the Employees list to select it, and then tap the New Record button.

- 5 In the Add Employees dialog box, select employees, and then tap OK.

Developing Quotes in Siebel Sales Handheld

When the customer is ready to purchase a product or service, you can develop a quote using Siebel Sales Handheld that includes specific prices for products and services with related payment terms.

The following topics related to quote development in Sales Handheld are included in this section:

- ["Scenario for Developing Quotes in Sales Handheld" on page 122](#)
- ["Creating Quotes in Sales Handheld" on page 122](#)
- ["Using Auto Quote in Sales Handheld" on page 123](#)
- ["Adding Quote Items in Sales Handheld" on page 124](#)
- ["Printing Quotes in Sales Handheld" on page 125](#)

Scenario for Developing Quotes in Sales Handheld

A mobile sales representative relies on quotes to create formal offers to clients for a variety of products and services that her company provides. Using Siebel Sales Handheld she can produce accurate offers at the customer site, with up-to-date product and pricing information. When details and pricing are finalized, the sales representative can print the quote and deliver it promptly to the customer.

Creating Quotes in Sales Handheld

Quotes includes effective dates, price lists, and discounts used in pricing products and services. Before any of this information can be added to a quote, however, the quote must be created with basic information.

To create a quote

- 1 Navigate to the Opportunities screen.
The My Opportunities list appears.
- 2 In the My Opportunities list, select the opportunity for which the quote will be generated.
- 3 From the Show drop-down list, select Quotes.
- 4 In the Opportunity Quotes view, tap the Quotes list to select it, and then tap the New Record button.

The new quote is automatically assigned a record identifier, a revision number, the default status of In Progress, and a created date.

- 5 In the Name field, enter a name for the quote.
When you tab to an adjacent field, the quote name becomes a hyperlink.
- 6 Drill down on the hyperlink in the Name field to display the More Info form where you can add quote details.

Using Auto Quote in Sales Handheld

If you are working with an opportunity for which the products and solutions have already been specified in the Opportunity Products view, there is a faster method to generate a quote. You can use the Auto Quote button.

When Auto Quote generates a quote from an opportunity, quote line items are created for each product under the opportunity that has the Auto Quote flag checked. The Quote Item fields are populated from the corresponding Opportunity Product's fields, as shown in [Table 22](#).

Table 22. Quote Item Fields Populated by Opportunity Product Fields

Opportunity Product Fields	Quote Item Fields
Product	Product
Product Quantity	Extended Quantity Requested
Write-In Product (not exposed in application)	Write-In Product (not exposed in application)
Expected Delivery Date	Requested Delivery Date (not exposed in application)
ID (not exposed in application)	Opportunity Product ID (not exposed in application)

In addition, information from the generated quote's Quote # field is copied to the Opportunity Products' Quote # field. The Part Number field of the generated Quote Item is determined by the quote item's product.

[Table 23](#) shows the quote record fields that are automatically completed when Auto Quote is used to create a quote.

Table 23. Quote Fields Completed with Auto Quote

Field	Value
Quote #	System generated
Revision	1
Name	Quote number, unless the user provides another value
Opportunity	The opportunity from which the quote is automatically generated

Table 23. Quote Fields Completed with Auto Quote

Field	Value
Account	The account for the opportunity
Account Site	The location of the account associated with the opportunity
Status	In Progress
Active	Checked
Currency	The currency code for the opportunity
Price List	The price list associated with the opportunity's account
Sales Rep	User ID
Effective	Current date
Through	Current date plus 30 days (30 days is determined by the QUOTE_EXPIRATION_PERIOD LOV)

To create a quote using Auto Quote

- 1** Navigate to the Opportunities screen.
The My Opportunities list appears.
- 2** In the My Opportunities list, select the opportunity for which the quote will be generated.
- 3** From the Show drop-down list, select Quotes.
- 4** In the Opportunity Quotes view, tap Auto Quote.
A new row appears in the Quotes list, with the Quote #, Revision, Status and Created date filled in.
- 5** Provide a quote name, edit other fields as necessary, and then drill down on the hyperlink in the quote Name field.
- 6** In the Quote detail form, enter additional information about the quote.
 - a** Select the applicable predefined Discount that will be applied to the quote.
 - b** Select the applicable predefined Price List.

NOTE: Auto Quote functionality is only available in the Opportunities screen Quotes view.

Adding Quote Items in Sales Handheld

Using the Quotes screen, you can add line items to quotes that you are developing. If the Auto Quote method is used, products associated with opportunities appear automatically as line items with any applicable discounts.

Line items can be used to:

- Add new products as line items

- Apply manual price adjustments to the line items using the Toggle button.

NOTE: Siebel Handheld does not support complex quotes (bundled line items). Only simple line items can be created.

To add line items

- 1** Navigate to the Opportunities screen.
The My Opportunities list appears.
- 2** In the My Opportunities list, select the opportunity with which the quote is associated.
- 3** In the Show drop-down list, select Quotes.
- 4** In the Opportunity Quotes view, locate the quote in the list and drill down on the Name hyperlink.
The quote detail form appears.
- 5** From the Show drop-down list, select Quote Items.
- 6** In the Quote Line Items view, tap the Line Items list, and then tap the New Record button.
- 7** In the Line Items list, complete the required fields.

Quote Line Item price fields are automatically populated based on the product's price in the parent quote's price list.

If you are entering more than one line item, repeat Step 6 and Step 7 until each line item has been entered. Tap the Toggle button to display a form that you can use to add Item discounts and other adjustments.

To delete line items

- 1** Navigate to the Quotes screen.
The My Quotes list appears.
- 2** In the My Quotes list, select the quote containing the line item that will be deleted, and choose Quote Items from the Show drop-down list.
- 3** In the Quotes Line Items view, select the quote item in the list.
- 4** From the Edit Menu, select Delete Record.

NOTE: Quote revisions are not supported on the handheld.

Printing Quotes in Sales Handheld

Once the customer has expressed significant interest, it is often appropriate to present a hard copy quote.

To print a quote

- 1** Navigate to the Quotes screen.
The My Quotes list appears.
- 2** In the My Quotes list, select the quote containing the line items that will be printed.
- 3** From the Show drop-down list, select Quote Items.
- 4** Align the infrared ports on the handheld device and the printer.
- 5** In the parent Quotes form, tap the Print button.

Managing Orders in Siebel Sales Handheld

After you have completed the initial quote, and the customer has agreed to the products and prices you have presented, you create a sales order.

The following order management topics are included in this section:

- ["Creating Orders in Sales Handheld" on page 126](#)
- ["Adding Order Line Items in Sales Handheld" on page 127](#)
- ["Entering Terms and Totals in Sales Handheld" on page 127](#)

Creating Orders in Sales Handheld

You can create orders from quotes manually or by using the Auto Order button.

To create an Auto Order from your quote

- 1** Navigate to the Quotes screen.
The My Quotes list appears.
- 2** In the My Quotes list, select the quote from which an order will be generated.
- 3** From the Show drop-down list, select Orders.
- 4** In the Quotes list, select the quote, and then in the Orders list tap AutoOrder.
A new record appears in the Orders list, with the order date, number, type, status and so on, filled in.
- 5** In the Orders list, drill down on the Order # hyperlink.
- 6** Tap the Orders Line Items list to select it, and then tap the New Record button.
A new row appears in the Line Items list.

- 7 Tap in the Products field.
The Pick Products dialog box appears.
- 8 Select the product to add as a line item, and tap OK.

To manually create an order

- 1 Navigate to the Orders screen.
- 2 The My Sales Orders list appears.
- 3 Tap the New Record button.
A new row appears in the Sales Orders list.
- 4 Complete the necessary fields for the new order record.
From the Show drop-down list, choose More Info to display a form where you can add more details.

Adding Order Line Items in Sales Handheld

Once the initial sales order is created, you can complete the line items that make up the order.

- 1 Navigate to the Orders screen.
The My Sales Orders list appears.
- 2 In the My Sales Orders list, select the order to which line items will be added.
- 3 From the Show drop-down list, select Line Items.
- 4 Tap the Line Items list to select it, and then tap the New Record button.
A new row appears in the Line Items list with the Line # and Status fields completed.
- 5 Complete the fields for the line item.
Repeat the previous step to add additional line items.

The Totals field automatically updates with the Quantity Requested total, and the Order record Item Total and Total fields get updated based on the sum of the Line Item Start Price and Net Price fields, respectively.

Entering Terms and Totals in Sales Handheld

After completing the line items, navigate to the Order Terms view to enter shipping and payment information for the order.

To add terms and totals

- 1 Navigate to the Orders screen.
The My Sales Orders list appears.
- 2 In the My Sales Orders list, select the order.
- 3 From the Show drop-down list, select Order Terms.
- 4 In the Order Terms view, tap the Terms form to select it.
- 5 In the Terms form, complete the necessary fields (such as Payment Terms, Ship Carrier, and so on).

NOTE: The basic Sales Handheld configuration does not include detailed shipping and billing fields. These fields are based on different business components and can be configured as required.

Tracking Expenses in Sales Handheld

You can track expenses and create expense reports using Siebel Sales Handheld.

The following expense management procedures are included in this section:

[“Creating an Expense Report in Sales Handheld” on page 128](#)

[“Submitting an Expense Report in Sales Handheld” on page 129](#)

Creating an Expense Report in Sales Handheld

You can create expense reports in Siebel Sales Handheld, then upload them to your server at the time of sync.

To create an expense report

- 1 Navigate to the Expenses screen.
The My Expense Reports list appears.
- 2 Tap the New Record button, and complete the necessary fields for the new record.
- 3 From the Show drop-down list, select More Info to view additional fields.

NOTE: You must complete the Submit To field or you will get an error message and your expense report will not be saved.

To add detailed line items

- 1 Navigate to the Expenses screen.
- 2 In the My Expense Reports list, locate the expense report record.

- 3 From the Show drop-down list, select Expense Items.
- 4 In the Expense Report Line Items view, tap the Line Items list, and then tap the New Record button.
- 5 In the new row, complete the necessary fields for the line item.
You can not enter Line Items whose Start or End Date is outside of the Expense Report period.

NOTE: Siebel Sales Handheld Expense Reports functionality does not currently support the Mileage expense type or detailed Hotel expense tax itemization. If these expense types are required, you must enter these items using the desktop Siebel Sales application.

- 6 Repeat the previous steps to add line items.
The cumulative total of all expense line items is automatically displayed in the Totals field.

Submitting an Expense Report in Sales Handheld

After creating an expense report, you'll then need to submit it for approval.

To submit an expense report

- 1 Navigate to the Expenses screen.
The My Expense Reports screen appears.
- 2 Select the desired expense report, then tap the Status field, and select submitted from the drop-down list.
The next time you sync to your enterprise system, the expense report will be submitted.

A Troubleshooting

This appendix addresses some of the common issues faced while deploying Siebel Handheld. The appendix presents troubleshooting tips in three areas:

- Installation
- Performance
- Log Files

The audience for this appendix is Siebel database administrators, system administrators, and application administrators.

["Installation" on page 131](#)

["Synchronization" on page 132](#)

["Log Files" on page 133](#)

["SQLTrace" on page 135](#)

["End User Error Messages" on page 136](#)

["Web Server Timeout Errors" on page 136](#)

["Performance" on page 136](#)

["Siebel Services" on page 139](#)

Installation

Siebel Handheld supports a specific and limited set of devices, handheld OS, desktop OS, server OS, server databases, and languages. This range of devices and platform support varies widely across the range of Siebel Handheld releases and must be carefully checked to confirm support. See *System Requirements and Supported Platforms* on Siebel SupportWeb for your Siebel application for information on supported Handheld OS, desktop OS, server OS, and server databases.

Client Installation, Backup, and Restore

If you run into problems while installing the Siebel Handheld application on client devices from a desktop PC, refer to the following checklist. Most installation problems are covered by this checklist.

- Is the device certified and supported? Refer to the system requirements and supported platforms documentation for the Siebel Handheld application.
- Confirm that the device has 64 MB of RAM with the majority of it available for the Siebel Handheld application.

- Is an ActiveSync connection running (green icon)? If not, check your computer to make sure that the serial or USB port is activated and functioning correctly.
- If previous versions of Siebel Handheld were installed on the device, did you uninstall the application? See ["Uninstalling the Siebel Handheld Application" on page 89.](#)

Siebel Handheld binaries may also be installed to a CompactFlash card to conserve (RAM) memory. The application will still be loaded into memory when it executes. To install on the CompactFlash card, set the ApplicationBinariesLocation and ApplicationDataLocation parameters in the setup.ini file. See ["Setting up Siebel Handheld Application Installation on a CompactFlash Card" on page 72.](#)

Siebel Handheld (application only - no data) may also be backed up to a CompactFlash card to aid in deployments. Using the built-in backup utility that comes with Compaq (QUtilities) and HP Jornada (HP Backup) devices, a backup image may be created which can then be restored onto other devices. The initial backup image should be made of a device that has *not* done an initial synchronization. An initial synchronization will still be required by each user to receive the configuration and data.

It is also possible to back up Siebel Handheld on a PC using the Backup/Restore feature within ActiveSync.

Synchronization

Synchronization problems can be caused by incorrect settings in the Siebel Handheld setup.ini or .cfg files. Be sure that application names, data sources, and SRFs are correct.

Make sure to set the URL setting (DSSURL) in the client setup.ini for direct server synchronization installations. Be sure to list the views (DefaultViews) in the application .cfg file. Also, do not forget to grant the user visibility to these views in the Application Administration > Responsibilities view.

NOTE: Check the log files and confirm the accuracy of the generated connect string.

Companion Sync Checklist

Use the following checklist to troubleshoot problems you encounter using Companion Sync.

- Is the latest version of ActiveSync (v.3.5 or later) installed and running?
- Is ActiveSync connected (green icon)?
- Do you have the correct data source defined in the handheld .cfg file?
- If you have problems logging in, check to make sure that you can use the same credentials to log into the desktop client.
- Remember to keep a 1:1 ratio of users to devices. Only a single user may log in to sync each device. Failure to do so causes data corruption.

Direct Server Sync Checklist

Use the following checklist to troubleshoot problems you encounter using Direct Server Sync.

- Did you install all client and server components successfully?
- Is there a PDA OM running on the Siebel Server?
- Did you bounce the IIS, SWE, and Siebel Server after installation?
- Do you have network access to the URL for DSS? Can you ping the IIS server from inside and, if applicable, from outside the firewall?
- Can you successfully run a SWE command?
- Do you have the correct DSS URL defined in the setup.ini file?
- Is the network connection working from the device? Try Pocket Internet Explorer.
- If you have problems logging in, check to make sure that you can use the same credentials to log into the desktop client.
- Remember to keep a 1:1 ratio of users to devices. Only a single user may log in to sync each device. Failure to do so causes data corruption.

Re-synchronizing Problems

Generally if, for whatever reason, synchronization is terminated, the end user is prompted with a message and the synchronization process ends. In this situation the synchronization session is allowed to close. However, if the connection with the server is unintentionally broken, the session may not have a chance to close before the connection is broken. Therefore, if the end user tries to immediately synchronize again, he may get an error message and may not be able to synchronize. Should this occur, the end user should wait for a period of time (generally, 15 minutes) to allow the session to time out and terminate. Once the session terminates, the end user should be able to synchronize again.

Log Files

This section discusses issues related to log files.

Direct Server Sync Log Files

To assist Siebel Technical Support, collect the following files when logging a Siebel Handheld service request. The following files are found on the machine where Siebel Server is installed:

- All server sync user files in the *Siebel Root\siebsrvr\hhsync\application directory\user id\node id* directory.
- Server NT application event log extract.
- Server NT system event log extract.

- All files in the *Siebel Root*\siebsrvr\log directory including CompName_task.log.
where CompName is the name of an application server component, and task is a Siebel task number. Each sync session is assigned a new Siebel task, so there will be many of these. An example "CompName" value is "SalesCE_enu" (note that language is part of the component name itself).
- All files from all subdirectories under the *Siebel Root*\siebsrvr\logarchive directory.
- Server perfmon log files (showing memory, network, disk performance), if available.

The following files are found on the machine where the Web Server (that is, IIS) is installed:

- SWE log files from *Siebel Root*\eappweb\log (all files).
- IIS server NT application event log extract.
- IIS server system event log extract.
- IIS server perfmon log files (showing memory, network, disk performance), if available.

Companion Sync Log Files

To assist Siebel Technical Support, collect the following log files when logging a Siebel Handheld service request. The following files are found on the companion PC where Siebel Mobile Web Client is installed:

- Client Siebel Handheld Sync log file: \log\syncmanager_log.txt.
- All files in the *Siebel Root*\client\hhsync\application directory\user id\node id directory.
- NT application event log extract.
- NT system event log extract.
- All files in the *Siebel Root*\client\log directory.
- Perfmon log files (showing memory, network, disk performance), if available.

Handheld Device Logs

The following log files are found in the /Program Files/Siebel Handheld directory on the handheld device:

- **dbimport_log.txt**—This file is a log of the database objects that were imported during synchronization. The file is located in the \Program Files\Siebel Handheld directory on the handheld client.
- **sql_stmt_log.txt**—This file logs all SQL statements generated by the application. You must set a parameter in the setup.ini file to turn this log on. The log file is located in the \Program Files\Siebel Handheld directory on the handheld client. See [“Deployment of Siebel Handheld” on page 61](#) for more information about setting the parameter.

- **ssa_errors_log.txt**—This file is a log of all system error messages. You must set a parameter in the setup.ini file to turn this log on. The log file is located in the \Program Files\Siebel Handheld directory on the handheld client. See “Deployment of Siebel Handheld” on page 61 for more information about setting the parameter.
- **syncmanager_log.txt**—This file contains all of the messages displayed on the Sync Manager dialog box as well as some basic information about synchronization, such as data source and connect string. You can set the logging level for this file using the SyncLogReportingLevel parameter in the setup.ini file.

For Direct Server Sync deployments, the file is located in the \Program Files\Siebel Handheld directory on the handheld client. For Companion Sync deployments, the file is located in the *Siebel Root*\client\log on the companion PC.

Logging Handheld Synchronization Errors

Siebel Handheld Sync logs all the strings that the user sees in the sync message window as well as many informational messages that do not get displayed in the UI. These informational messages are used to help track down where an error occurred. Siebel Handheld Sync determines which messages get logged based on a value stored in the registry under the key SyncLogReportingLevel. The values range from 0 to 4; 0 logs all error messages and strings that the user sees, and 4 logs all data that Siebel Handheld Sync sends and receives.

If Siebel Handheld Sync fails for some reason, check the syncmanager_log.txt file immediately after the failure. If you need more detail, increase the logging level and run Siebel Handheld Sync again. Use the LoggingLevels parameter in the setup.ini file to change the logging level. Furthermore, each time a user synchronizes, the syncmanager_log.txt file is overwritten with the new data.

SQLTrace

Use SQLTrace for diagnostic purposes if you encounter serious configuration errors or performance problems and cannot otherwise diagnose the problem. The problem may quickly become apparent in the log entries from SQL tracing.

To enable SQL tracing

- 1 Log into svrvmgr from a (m:\siebel\bin\w32ud) prompt.
- 2 Run: change evtloglvl ObjMgrSqlLog=4 for comp [OMName], where [OMName] = the OM name (for example, <ApplicationName>CEObjMgr_enu).
- 3 Log entries are written to <OMName>ObjMgr_enu as described in “Log Files” on page 133.

NOTE: SQL tracing only logs SQL statements for one user at time. SqlTrace is applied to the first user who synchronizes after tracing is enabled.

CAUTION: When SQL tracing is enabled, synchronization is severely and adversely affected. Therefore, it is recommended that you turn SQL tracing on for a limited time to diagnose a specific problem, then turn SQL tracing off.

End User Error Messages

End users may encounter error messages when they synchronize their data. For more information on these messages, see ["Synchronization Troubleshooting with the Siebel Handheld Client"](#) on page 105.

Web Server Timeout Errors

If synchronization times are long due to the size of the database file or the speed of the network connection, your end users may encounter Web server timeout errors and synchronization failures. First try to resolve this problem by reducing the size of your extract and configuring your server performance. If after doing this, your end users continue to experience timeout errors, then increase the timeout parameter on IIS for the default Web Server.

Follow the procedure for your platform to change the timeout parameter.

To change the timeout parameter on Windows 2000

- 1 From the Start menu, select Programs > Administrative Tools > Internet Services Manager.
- 2 From the Internet Information Services window, select the local machine, right-click on the Default Web Site, and select Properties from the pop-up list.
- 3 From the Web Site Properties window, select the Web Site tab.
- 4 Under the Connections heading, locate the Connection Timeout property and increase the number of seconds.
- 5 Click OK.

To change the timeout parameter on Windows NT

- 1 From the Start menu, select Programs > Windows NT 4.0 Option Pack > Microsoft Personal Web Server > Internet Service Manager.
- 2 Under Internet Information Server, right-click on the Default Web Site and select Properties from the pop-up list.
- 3 From the Web Site Properties window, select the Web Site tab.
- 4 Under the Connections heading, locate the Connection Timeout property and increase the number of seconds.
- 5 Click OK.

Performance

This section discusses ways you can optimize your client performance, server performance, and network performance.

Client Performance

Client performance is affected primarily by the device capability (minimum 206 MHz processor and 64 MB RAM), configuration, and the quantity of data loaded onto the device. In general, screen-to-screen and view-to-view navigation times of 3 to 4 seconds or less should be considered normal.

It is strongly recommended that customers follow these general guidelines to optimize the performance of their handheld applications:

- Keep configuration under 30 views.
- Keep RML file size under 1.75 MB.
- Keep database files (dbfile.txt) under 2 MB.
Use filters as outlined in the Siebel 2000 Handheld Synchronization Technical Note.
- Keep the number of records for each business component under 2,500.
- Avoid installing other applications on the device at the same time.
- Users should synchronize their data frequently.

Additional configuration information can be found in the Siebel Technical Note 405, *Siebel Handheld Synchronization*.

The Professional Services Mobile eBusiness Competency group has a Siebel Handheld Quickstart program that is mandatory for all new Siebel Handheld customers to assess their configuration and deployment.

The Siebel Handheld client will benefit from periodic closing and restarting the application to release memory consumed by the handheld operating system. Use File > Exit in the menu to exit from the Siebel Handheld application.

If an external VGA driver is or has been loaded on the device in the past and is no longer needed, be sure to unload it, because it is known to have significant performance impacts on handheld devices.

Server Performance

Server performance affects the performance and scalability of Direct Server Sync processes. Customers should engage Expert Services to do a Scalability Review. The following guidelines are general in nature and pertain to the Siebel Handheld sync components running on a Siebel Server:

- Use Performance Monitor to track memory and processor performance on the Siebel server.
- Make sure that the Servers (IIS, GW, OM and DB) are on the same high speed LAN segment.
- Siebel Handheld Sync components will stress Siebel Server and database performance because of the intensive interactions during large concurrent synchronizations.
- Estimate that 64 MB is used per Siebmtsh.exe instance.
- To calculate the theoretical maximum concurrent users:
 - $\text{Numusers} = \text{Server_Memory} * \text{threads_per_process_ratio} / 64 \text{ MB}$.

- Optimize the Threads per Process Ratio (Max Tasks/Max MT Servers) per Technical Note 405, *Siebel Handheld Synchronization*.
- Set Max Tasks=Max. number of concurrent users (for example, 150).
- Set MinMTServers=MaxMTServers (for example, 30 for 5:1 ratio, if this is determined to be appropriate).

To optimize and tune a Siebel DB server:

- Use Performance Monitor to track memory and processor performance on the DB server.
- Turn on SQL tracing and search for long-running SQL calls.
- Estimate 64 MB of RAM for each concurrent user.
- Consider creating indexes to tune the queries (only performed with the assistance of Siebel Expert Services).
- Consider using a RAID 0+1 disk array with an expanded number of spindles to optimize database performance.

NOTE: Make sure that DB Server settings are set to recommended values. Timeouts should be set at the Siebel Server. Be careful that the timeout is set longer than the longest SQL query.

Network Performance

The condition of the network affects Direct Server Sync performance and scalability. In general, a low-latency, high-bandwidth network is preferred with dedicated rather than shared network connections. The following are general network considerations:

- Make sure there is adequate bandwidth throughout the entire round-trip of network packets and estimate where bottlenecks will occur due to high concurrent load. For example, if 50 users are concurrently synchronizing 1 MB each, 50 MB of data must pass through the network. If this data is passing through a single leased 56 KB per second line, then this data will minimally take $500,000 \text{ KB} / 56 \text{ KB/sec} = 8928 \text{ seconds} = 148 \text{ minutes}$. In reality, a 56 KB per second line will offer only 30-40 KB per second average throughput, which causes further bandwidth constraints. Check the total available bandwidth of network providers (private or public ISP).
- Verify that you have low latency lines with ping round trips of less than 1 second (1000 ms) with no dropped packets.
- Verify if roundtrips occur with less than 10 hops.
- Check the actual throughput of network connections by performing simple file transfers with no Siebel software.
- Nonvalidated VPN software from third parties accounts for 30 to 60 percent of additional packet overhead because of the encryption.

Network problems can usually be resolved by working with network providers to size network connections and optimize network routing. Consider the use of burst networks, quality of service contracts, private networks, and dedicated modem banks directly into a high-speed LAN environment. Noisy phone lines in some countries may benefit from the use of an external modem card from Xircom or Pretec instead of the built-in modem on the HP Jornada 720.

Siebel Services

You may wish to consult experts who have experience designing and configuring handheld applications, and who are knowledgeable about optimizing the performance of the applications.

Siebel Professional Services

To make deployment planning and implementation successful, Siebel Handheld customers are encouraged to engage the Siebel Mobile eBusiness Competency group. The Siebel Professional Services team has developed a Siebel Handheld Quickstart solution which defines the strategy, approach, and roadmap for successful Siebel Handheld deployments. Working directly with experienced handheld experts from the Mobile eBusiness Competency, customers can develop a complete deployment strategy, approach, and roadmap to facilitate their handheld implementation in a short time period.

Siebel Expert Services

All Siebel Systems customers should work with Siebel Expert Services to conduct detailed configuration and hardware sizing reviews. This helps customers make sure they have implemented the most effective and efficient solutions possible. Siebel Handheld customers benefit by making sure Siebel Handheld applications are configured according to best practices and that server environments are properly designed.

B Screens and Views

Siebel Handheld Client supports a subset of the screens and views supported by the Siebel Web Client application. Other screens and views can be configured for your Siebel Handheld Client application if they are based on currently supported classes. Application developers and application administrators will find the information in this appendix useful.

If you configure screens and views based on unsupported classes, you may see anomalous results. For information on how to determine the classes used by other screens and views, see *Object Types Reference*.

Screens and Views

The screens and views shipped with the Siebel Sales Handheld sample application are shown in [Table 24](#).

Table 24. Siebel Sales Handheld Screens and Views

Screen	View Name on UI	View Name in Siebel Tools (salesce.cfg)
Contacts	My Contacts	SHCE Sales Visible Contact List View
	More Info	SHCE Sales Contact Details View
	Personal Contacts	SHCE Sales Personal Contact List View
	Opportunities	SHCE Sales Contact Detail - Opportunities View
Accounts	My Accounts	SHCE Sales Account List View
	My Team's Accounts	SHCE Sales Manager's Account List View
	More Info	SHCE Sales Account Detail View
	Activities	SHCE Sales Account Detail - Activities View
	Contacts	SHCE Sales Account Detail - Contacts View
	Addresses	SHCE Sales Account Detail - Business Address View
	Opportunities	SHCE Sales Account Detail - Opportunities View
Opportunities	My Opportunities	SHCE Sales Opportunity List View
	My Team's Opportunities	SHCE Sales Manager's Opportunity List View
	More Info	SHCE Sales Opportunity Detail View
	Activities	SHCE Sales Opportunity Detail - Activities View

Table 24. Siebel Sales Handheld Screens and Views

Screen	View Name on UI	View Name in Siebel Tools (salesce.cfg)
	Contacts	SHCE Sales Opportunity Detail - Contacts View
	Quotes	SHCE Sales Opportunity Quote View
	Products	SHCE Sales Opportunity Detail - Products View
Employees	All Employees	SHCE Sales Employee List ReadOnly View
	Employees - More Info	SHCE Sales Employee Detail View
Calendar	Daily	SHCE Sales Calendar Daily View - My
	Weekly	SHCE Sales Calendar Weekly View - My
	Monthly	SHCE Sales Calendar Monthly View - My
	Employee Participants	SHCE Sales Calendar Employee Participants View
	Contact Participants	SHCE Sales Calendar Contact Participants View
	Note: This view does not have a view name in the UI. It is a drill-down view.	SHCE Sales Calendar Add/Modify View
Activities	My Activities	SHCE Sales Activity List View
	More Info	SHCE Sales Activity Detail View
	Contacts	SHCE Sales Activity Contact Participants View
	Employees	SHCE Sales Activity Employee Participants View
Expense Reports	My Expense Reports	SHCE Sales Expense List View
	More Info	SHCE Sales Expense List Detail View
	Expense Items	SHCE Sales Expense Item List View
Quotes	My Quotes	SHCE Sales Quote List View
	More Info	SHCE Sales Quote List Detail View
	Quote Items	SHCE Sales Quote Detail View
	Orders	SHCE Sales Quote Orders View
Orders	My Sales Orders	SHCE Sales Order Entry - My Orders View (Sales)
	More Info	SHCE Sales Order Entry - Detail Orders View (Sales)
	Line Items	SHCE Sales Order Entry - Line Items View (Sales)
	Order Terms	SHCE Sales Order Entry - Order Terms View (Sales)

Table 24. Siebel Sales Handheld Screens and Views

Screen	View Name on UI	View Name in Siebel Tools (salesce.cfg)
Products	All Products	SHCE Sales Product List View
	More Info	SHCE Sales Product Detail View
Pricing	Price Lists	SHCE Sales Price List View
	More Info	SHCE Sales Price List Detail View
	Line Items	SHCE Sales Price List Line Item View

C

Business Components and Classes

Siebel Handheld Client supports a subset of the business components and classes supported by the Siebel Web Client application. This appendix lists the supported business components, business component classes, and applet classes.

["Supported Business Components for Siebel Handheld" on page 145](#)

["Business Component Classes" on page 146](#)

["Applet Classes" on page 147](#)

Supported Business Components for Siebel Handheld

Table 25 lists the supported Business Components for Siebel Sales Handheld.

Table 25. Siebel Sales Handheld Business Components

Supported Business Components
Account
Action
Business Address
Contact
Contact (All)
Contact (Personal)
Employee
Employee (MM)
Expense
Expense Item
Internal Product
Opportunity
Opportunity Product
Order Entry - Line Items
Order Entry - Orders

Table 25. Siebel Sales Handheld Business Components

Supported Business Components
Price List
Quote
Quote Item

Business Component Classes

Table 26 lists the supported Business Component classes for Siebel Sales Handheld.

Table 26. Siebel Sales Handheld Business Component Classes

Supported Business Component Classes
CSSBCActivity
CSSBCBase
CSSBCBCExpitm
CSSBCExprpt
CSSBCLineItem
CSSBCOppty
CSSBCOrder
CSSBCPriceList
CSSBCProdBuyNow
CSSBCProdRev
CSSBCQuote
CSSBCQuoteItem
CSSBCUser

Applet Classes

You may create additional screens and views for your handheld application. Any new screens and views must be based on classes and Business Components that are supported for the Sales Handheld application. Refer to [Table 27](#) for the supported applet classes.

Table 27. Siebel Sales Handheld Applet Classes

Supported Applet Classes
CSSFrame
CSSFrameAlarmList
CSSFrameBase
CSSFrameCECaAddModify
CSSFrameCEGridDay
CSSFrameCEGridMonth
CSSFrameCEGridWeek
CSSFrameCEHome
CSSFrameCEMultiPart
CSSFrameList
CSSFrameListBase
CSSFrameListExpitm
CSSFrameListQuote
CSSFrameListQuoteItem
CSSFrameQuote

Configuring Siebel eBusiness Applications

D

User Properties and Methods

This appendix documents the handheld-specific user properties and methods for the Siebel Handheld application.

User Properties

Table 28. User Properties

Name	Comments
HandheldSyncPickMode	User property on a field of a business component. When set to NoFail, turns Extended Pick processing ON. See "Extended Pick Processing in Siebel Handheld" on page 79 for more information.
HandheldSyncInsertMode	User property on a business component. When set to FailOnError, enables Extended Insert processing. See "Extended Insert Processing in Siebel Handheld" on page 82 for more information.
OverridePopupVisibility	Overrides Popup Visibility Type on a business component. Use OverridePopupVisibility to change the visibility on a picklist without changing the Popup Visibility Type. See "Overriding the Popup Visibility" on page 60 for more information.
View	Used with the GotoView method. Specifies the view to be displayed when navigating from one view to another. See "Applet Focus Behavior" on page 23 for more information.

Global User Properties

The following user properties apply to all business components.

Table 29. User Properties

Name	Description
HandheldSyncPickMode	User property on a field of a business component. When set to NoFail, turns Extended Pick processing ON. See "Extended Pick Processing in Siebel Handheld" on page 79 for more information.
HandheldSyncInsertMode	User property on a business component. When set to FailOnError, enables Extended Insert processing. See "Extended Insert Processing in Siebel Handheld" on page 82 for more information.

Methods

The following details methods you can use for your Siebel Handheld application.

AutoQuote

The AutoQuote method generates a quote from an opportunity. The opportunity may contain one or more products. A quote item is generated for each product in the opportunity that has the AutoQuote field flag selected.

When the AutoQuote method is executed, the quote business component fields are populated with the values shown in [Table 30](#).

Table 30. AutoQuote Method

Field	Value
Quote Number	This field is assigned a system-generated value
Revision	1
Name	Quote Number (or user-provided name)
Opportunity	Opportunity from which AutoQuote was called
Account	Opportunity's account
Account Location	Opportunity's account location
Status	In Progress
Active	Flag is set to on
Currency	Opportunity's currency code
Price List	Opportunity's price list
Sales Rep	User's login
Start Date	Today's date
End Date	Today's date + 30 days (30 days is determined by the QUOTE_EXPIRATION_PERIOD LOV)

The Quote Item business component fields are populated from the corresponding Opportunity Product's business component fields as shown in [Table 31](#):

Table 31. Population of Fields in Quote Item View

Source Field From Opportunity Product View	Destination Field Quote Item View
Product	Product
Product Quantity	Extended Quantity Requested
Write-In Product (Not exposed)	Write-In Product (Not exposed)
Expected Delivery Date	Requested Delivery Date (Not exposed)
ID (Not exposed)	Opportunity Product ID (Not exposed)

Fields that are noted as "Not exposed" do not appear in the user interface.

In addition, the Quote Number field in the generated quote is copied back to the Opportunity Product view ([Table 32](#)).

Table 32. Population of Fields in Opportunity Product View

Source Field From Quote View	Destination Field To Opportunity Product View
Quote Number	Quote Number (Not exposed)

AutoOrder

The AutoOrder method generates an order from a quote. AutoOrder creates a corresponding line item for each quote item in the quote. The Order Entry Line Items business component fields are populated with the corresponding Quote Item business component fields as shown in [Table 33](#).

Table 33. Population of Fields in Order Entry - Line Items View

Source Field From Quotes – Quote Items View	Destination Field To Order Entry - Line Items View
Extended Quantity Requested	Extended Quantity
Product	Product
Discount Amount (Not exposed)	Discount Amount (Not exposed)
Discount Percent	Discount Percent (Not exposed)

Table 33. Population of Fields in Order Entry - Line Items View

Source Field From Quotes – Quote Items View	Destination Field To Order Entry - Line Items View
Description (Not exposed)	Description (Not exposed)
Requested Delivery Date (Not exposed)	Due Date (Not exposed)
Unit Price (Not exposed)	Unit Price (Not exposed)
Volume Discount Id (Not exposed)	Volume Discount Id (Not exposed)
Volume Discount Item Id (Not exposed)	Volume Discount Item Id (Not exposed)
Base Price	Base Price
Adjusted List Price	Adjusted List Price
Covered Product Id (Not exposed)	Covered Product Id (Not exposed)

If the quote item’s product is a service product, then the following fields are also copied from the Quotes – Quote Items view to the Order Entry - Line Items view (Table 34).

Table 34. Copied Fields for Service Products

Source Field From Quote – Quote Items View	Destination Field To Order Entry - Line Items View
Covered Quote Item Id (Not exposed)	Covered Quote Item Id (Not exposed)
Service Price Amount (Not exposed)	Service Price Amount (Not exposed)
Service Price Percent (Not exposed)	Service Price Percent (Not exposed)
Service Price Method (Not exposed)	Service Price Method (Not exposed)

When AutoOrder is executed, the quote’s Status field is updated to “Order Placed.”

When AutoOrder is executed, the following fields in the Order Entry - Orders business component are pre-populated (automatically populated?) as shown in Table 35.

Table 35. Pre-populated Fields in Order Entry - Orders Business Component

Order Entry - Order Business Component Field	Value
Order Number	System-generated value
Account	Quote’s Account
Account Location	Quote’s Account Location
Contact Last Name	Quote’s Contact Last Name

Table 35. Pre-populated Fields in Order Entry - Orders Business Component

Order Entry - Order Business Component Field	Value
Contact First Name	Quote's Contact First Name
Order Priority	Medium
Status	Pending
Order Type	Sales Order
Active	Set to Active (Turned on? Flag is set to on?)
Order Date	Today's date
Discount	Quote's Discount
Price List	Quote's Price List
Currency Code	Quote's Currency Code
Requested Ship Date	Quote's Requested Ship Date (Not exposed)
Created	Today's date
Created By Name	User's login ID
Discount Amount (Not exposed)	Quote's Discount Amount (Not exposed)
Primary Organization Id (Not exposed)	Quote's Primary Organization Id (Not exposed)

E

Print Tagging Language

This chapter describes the print tagging language that is used to create print templates for your handheld device.

The audience for this appendix is Siebel application developers.

[“Overview of Siebel Handheld Print Tagging Language” on page 155](#)

[“Using Variables in Print Templates” on page 171](#)

[“Using Variables in Print Templates” on page 171](#)

Overview of Siebel Handheld Print Tagging Language

You can create the print template file in any text editor.

- Tags are enclosed in angle brackets and identified with the keyword TAG, followed by a colon. For example: <TAG:>
- Parameters are specified with a keyword, followed by an equals sign. Arguments are in uppercase, surrounded by quotation marks. For example, Font = "FONT FACE"
- Values are in uppercase and lowercase, surrounded by quotation marks. For example: Font = "Helvetica"
- Tags may appear in any order in the file. The only required tag is the Title tag.
- Variables within a print template must be uniquely named. Variable names must be one-word strings and spaces are not allowed.

The following tags are used to specify the format of the print output, which applets are included, and the query that is executed:

- Applet—Specifies which applets are used in the document.
- Comment—Adds comments that do not appear in the final document.
- Divider—Adds visual lines to visually separate different parts of the document.
- Footer—Adds information such as page numbers, date, and time.
- Format—Specifies characteristics such as font, boldface, italics, and underline.
- Header—Adds information such as page numbers, date, and time.

- Page Break—Specifies a break in the text, forcing the text that follows to appear on the next page.
- Picture—Adds graphic images to the document.
- Title—Specifies a name for the template that appears in the print job list.

In addition, you may add static text in the print template.

The following print tags allow you to calculate additional information and add it to your reports:

- GetTotal—Calculates the total for a column of data.
- GetField—Gets the value of a field.
- GetCount—Calculates the number of records.

You can also calculate dates and times using the GetDate and GetTime tags, and you can retrieve the value of the registry using GetRegistry.

All of this information is stored in variables that you specify. In addition, you can assign any value to a variable using the SetVariable tag. You can present this information in your report using the Cell and EndofLine tags to create tables of information. See [“Using Variables in Print Templates” on page 171](#) for an example of how variables can be used to present information in print templates.

Applet

Description

Specifies the applet to be printed.

Usage

Any data that appears in your document must be generated from the applets in the view. Therefore, you must create applets that will produce the data required for your document.

Use the Applet tag to specify any number of list or form applets within the template and to locate the applet in your document. In the form view, a maximum of two fields per row are supported.

Syntax

```
<TAG:Applet Name="APPLET NAME" Query="QUERY STRING" Caption="CAPTION"  
Headerdivider="HEADERDIVIDER" Recorddivider="RECORDDIVIDER" Wrap="WRAP">
```

Parameter	Description
TAG:Applet	(Required) Applet tag indicator.
APPLET NAME	(Required) Applet name as defined in Siebel Tools.

Parameter	Description
QUERY STRING	<p>(Optional) Specifies the query string directly set to the business component supporting the document.</p> <p>If the query string is not specified, the currently active query string in the view is applied to expose the relevant records.</p>
CAPTION	<p>(Optional) Specifies whether the captions in the form applets are suppressed.</p> <p>Valid values are TRUE (default) and FALSE. This parameter does not apply to list applets. Column headings in list applets are always enabled.</p>
HEADERDIVIDER	<p>(Optional) Specifies whether a divider is printed below the column heading in list applets.</p> <p>Valid values are TRUE and FALSE (default). This parameter does not apply to form applets.</p>
RECORDDIVIDER	<p>(Optional) Specifies whether a horizontal divider is printed between records in list applets.</p> <p>Valid values are TRUE and FALSE (default). This parameter does not apply to form applets.</p>
WRAP	<p>(Optional) Specifies whether text field values are word wrapped.</p> <p>Valid values are TRUE and FALSE (default). This parameter does not apply to numeric fields.</p>

Example

<TAG:Applet Name="Order List" Headerdivider="TRUE">

Cell

Description

Prints the string stored in STRING or VARIABLE NAME at the specified location on the current line.

Usage

Use the Cell tag to create cells of data in a row in a table. Use it with the EndOfLine tag. If the data exceeds the width of the cell specified by Startat and Endat, it wraps to the next line.

Syntax

<TAG:Cell Startat="START" Endat="END" Name="STRING" Variable="VARIABLE NAME" Align=ALIGNMENT"

Parameter	Description
TAG:Cell	(Required) Required tag indicator.
START	(Required) Specifies the starting point of the cell, expressed as a percentage of the printable page width. For example, if START =10, then the cell starts at the point that is 10% from the left edge of the printable width.
END	(Required) Specifies the end point of the cell, expressed as a percentage of the printable page width. For example, if END=50, then the cell ends at the point that is 50% from the left edge of the printable width.
STRING	(Optional) String value. If Variable is not specified, then String is a required parameter.
VARIABLE NAME	(Optional) Name of variable where the value is stored. If String is not specified, then Variable is a required parameter.
ALIGNMENT	(Optional) Specifies the alignment of the string. Valid values are LEFT (default), CENTER, and RIGHT.

Example

```
<TAG:Divider Weight="3" Startat="20" Endat="80">
<TAG:Cell Startat="0" Endat="50" name="TOTAL:" Align="RIGHT">
<TAG:Cell Startat="50" Endat="100" Variable="vvv1total" Align="RIGHT">
<TAG:EndOfLine>
<TAG:Cell Startat="0" Endat="50" name="TOTAL Defective:" Align="RIGHT">
<TAG:Cell Startat="50" Endat="100" Variable="vvvDefectiveTotal" Align="RIGHT">
<TAG:EndOfLine>
<TAG:Cell Startat="0" Endat="50" name="TOTAL Good:" Align="RIGHT">
<TAG:Cell Startat="50" Endat="100" Variable="vvvGoodTotal" Align="RIGHT">
<TAG:EndOfLine>
<TAG:Cell Startat="0" Endat="50" name="Defective Count:" Align="RIGHT">
<TAG:Cell Startat="50" Endat="100" Variable="vvvDefectiveCount" Align="RIGHT">
<TAG:EndOfLine>
<TAG:Cell Startat="0" Endat="50" name="Good Count:" Align="RIGHT">
```

```
<TAG:Cell Startat="50" Endat="100" Variable="vvvGoodCount" Align="RIGHT">
<TAG:EndOfLine>
<TAG:Cell Startat="50" Endat="100" Variable="vvv3reg">
<TAG:EndOfLine>
<TAG:Cell Startat="50" Endat="100" Variable="vvv5str">
<TAG:EndOfLine>
<TAG:Cell Startat="0" Endat="30" Variable="vvv4date">
<TAG:Cell Startat="30" Endat="70" Variable="vvv4longdate">
<TAG:Cell Startat="70" Endat="100" Variable="vvv8time">
<TAG:EndOfLine>
```

Comment

Description

Adds code comments to the print template.

Usage

Use to add explanatory notes or documentation to explain and maintain the print template. Comment tags are ignored during printing and do not appear in the printed document.

Syntax

```
<REM: COMMENT>
```

Parameter	Description
REM	(Required) Comment tag indicator.
COMMENT	(Optional) Comment text.

Example

```
<REM: Quotation Print Template. This template includes four applets.>
```

Divider

Description

Renders a horizontal line across the width of the page.

Usage

Use to visually separate the different sections of your document. The Divider tag can be used between other tags; therefore, you may add a line between two applets. However, you cannot embed a Divider within an applet.

Syntax

```
<TAG:Divider Weight="WEIGHT" Startat="START" Endat="END">\
```

Parameter	Description
TAG:Divider	(Required) Divider tag indicator.
WEIGHT	(Optional) Specifies line thickness. Valid values are 1–5. The default value is 1, which produces a line 0.2 mm wide. Increasing the value by 1 increases the width by 0.2 mm. A 5 produces a line that is 1 mm wide.
START	(Optional) Percentage that specifies the starting point of the line. The default is 0%, the farthest left point.
END	(Optional) Percentage that specifies the end point of the line. The default is 100%, the farthest right point.

Example

```
<TAG:Divider Weight="2" Startat="20" Endat="80">
```

EndOfLine

Description

Specifies the end of a row and advances to the next line.

Usage

Use to create rows of data in a table. Used with the Cell tag.

Syntax

```
<TAG:EndOfLine>
```

Example

```
<TAG:Cell Startat="0" Endat="50" Name="TOTAL:" Align="RIGHT">
<TAG:Cell Startat="50" Endat="100" Variable="vvv1total" Align="RIGHT">
<TAG:EndOfLine>
```

Footer

Description

Adds footer information such as page numbers, the current date, and the current time.

Usage

You may, for example, always want the text "Thank you for your business!" to appear on the bottom of your receipts. If so, you may include this text in a Footer tag.

The Footer tag may be specified anywhere in the template file; however, it will always appear at the very bottom of your document. Only one Footer tag is applied to the document. If you have multiple Footer tags in the file, only the last Footer tag is used; any other Footer tags are ignored.

If you include a Footer tag in your template, then you must set the BottomMargin in setup.ini to a minimum of 20.

The footer has three sections, Left, Center, and Right, which are used to position the information in the footer.

The text in the footer is formatted in 10 point, Helvetica font. If Helvetica is not available on your system, the default font is used. You cannot customize text formatting of the Footer tag. The Format tag does not affect the formatting of the footer.

Syntax

```
<TAG:Footer Left="DATA" Center="DATA" Right="DATA">
```

Parameter	Description								
TAG:Footer	(Required) Footer tag indicator.								
DATA	(Optional) Static text or one of the following data tags:								
	<table border="1"> <thead> <tr> <th>Data tag</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td><page></td> <td>Page number</td> </tr> <tr> <td><date></td> <td>Date of the printing</td> </tr> <tr> <td><time></td> <td>Time of the printing</td> </tr> </tbody> </table>	Data tag	Description	<page>	Page number	<date>	Date of the printing	<time>	Time of the printing
Data tag	Description								
<page>	Page number								
<date>	Date of the printing								
<time>	Time of the printing								

Example

```
<TAG:Footer Left="<date>" Right="<page>"
```

Format

Description

Specifies the characteristics of the text—the typeface or font, whether the text is in boldface, italics, or underlined, and the text alignment.

Usage

The font specification specifies the characteristics of all text that follows the tag until the next Format tag.

The text alignment tag (Align) behaves somewhat differently. When the applet is rendered, the field alignment specification takes precedence over the Align parameter.

Syntax

```
<TAG:Format Face="FONT FACE" Size="FONT SIZE" Bold="BOLD" Italic="ITALIC" Underline="UNDERLINE" Align="TEXT ALIGNMENT">
```

Parameter	Description
TAG:Format	(Required) Format tag indicator.
FONT FACE	(Required) Specifies the typeface of the text. Any typeface installed on the handheld device may be specified. There is no default for this parameter.
FONT SIZE	(Required) Specifies the text size. Any installed font size for an installed typeface on the handheld device may be specified. There is no default for this parameter.
BOLD	(Optional) Specifies whether the text is in bold. Valid values are TRUE or FALSE (default). If TRUE, text is set to bold.
ITALIC	(Optional) Specifies whether the text is in italic. Valid values are TRUE or FALSE (default). If TRUE, text is set to italic.
UNDERLINE	(Optional) Specifies whether the text is underlined. Valid values are TRUE or FALSE (default). If TRUE, text is set to underline.
TEXT ALIGNMENT	(Optional) Specifies the text alignment. Valid values are LEFT (default), RIGHT, and CENTER.

Example

```
<TAG:Format Face="Helvetica" Size="10">
```

GetCount

Description

Calculates the number of records in the selected rows and assigns this value to a variable.

Usage

Use GetCount to calculate the number of records and print this value in your report.

Syntax

```
<TAG:GetCount Appletname="APPLET NAME" Query="QUERY STRING" Variable="VARIABLE NAME">
```

Parameter	Description
TAG:GetCount	(Required) Required tag indicator.
APPLET NAME	(Required) Name of the applet.
QUERY STRING	(Optional) Search specification for the rows to be included in the row set. If not specified, the current search specification is used. The syntax for the query string is: Field Name Query Statement. You may specify one or more query strings separated by a vertical bar (). For example, Query="Name LIKE 'Sieb*'" "Location LIKE 'H*'"
VARIABLE NAME	(Required) Name of variable where the value is stored.

Example

```
<TAG:GetCount Appletname="CS HH Product Bucket List Applet" Query="Status|Good" Variable="StatusGood">
```

GetDate

Description

Gets the current date, offsets the date by the number of days specified in Dayoffset, and stores the result in a variable.

Usage

Use GetDate to print a specific date in your report.

Syntax

<TAG:GetDate Dayoffset="NUMBER OF DAYS" Variable="VARIABLE NAME" Logformat="DATE FORMAT">

Parameter	Description
TAG:GetDate	(Required) Required tag indicator.
NUMBER OF DAYS	(Optional) Number of days by which the current date is offset. For example, -100 subtracts 100 days from the current date; 100 adds 100 days to the current date. The default is 0.
VARIABLE NAME	(Required) Name of variable where the value is stored.
DATE FORMAT	(Optional) TRUE prints the date in long date format (for example, Monday, February 11, 2002). FALSE prints the short date format (for example, 2/21/02). The default is FALSE.

Example

<TAG:GetDate Longformat="TRUE" Variable="LongDate">

GetField

Description

Gets the value of the specified column of the first row of selected rows and assigns the result to a variable.

Usage

Use GetField to print a value without developing a print applet. Design the query and sort strings so that the desired record is the first record in the selected rows. GetField only allows you to get the value in the first record.

Syntax

<TAG:GetField AppletName="APPLET NAME" Fieldname="FIELD NAME" Query="QUERY STRING" Sort="SORT STRING" Variable="VARIABLE NAME">

Parameter	Description
TAG:GetField	(Required) Required tag indicator.
APPLET NAME	(Required) Name of the applet.
FIELD NAME	(Required) Name of the field or column.
QUERY STRING	(Optional) Search specification for the rows to be included in the total. If not specified, the current search specification is used.

Parameter	Description
SORT STRING	(Optional) Sort specification. If not specified, the current sort specification is used. The syntax is: Field Name [ASC][DESC]. The default is ASC (Ascending). For example: Sort="Account DESC, Date". In the example, the Account field is sorted in descending order, then the date field is sorted in ascending order.
VARIABLE NAME	(Required) Name of variable where the value is stored.

Example

```
<TAG:GetField AppletName="CS HH Product Bucket List Applet" Fieldname="Quantity" Variable="ProdBucketListField">
```

GetRegistry

Description

Gets a value in the registry for Siebel Handheld and assigns it to a variable.

Usage

Use GetRegistry to print the contents of the registry key in your report.

Syntax

```
<TAG:GetRegistry Name="REGISTRY NAME" Variable="VARIABLE NAME">
```

Parameter	Description
TAG:GetRegistry	(Required) Required tag indicator.
REGISTRY NAME	(Required) Value the registry.
VARIABLE NAME	(Required) Name of variable where the value is stored.

Example

```
<TAG:GetRegistry Name="InstallDir" Variable="Registry">
```

GetTime

Description

Gets the current time, offsets the time by the number of seconds specified in Secondoffset, and assigns the result to a variable.

Usage

Use GetTime to print a specific time in your report.

Syntax

```
<TAG:GetTime Secondoffset="NUMBER OF SECONDS" Variable="VARIABLE NAME">
```

Parameter	Description
TAG:GetTime	(Required) Required tag indicator.
NUMBER OF SECONDS	(Optional)Number of seconds by which the current time is offset. For example, -100 subtracts 100 seconds from the current time; 100 adds 100 seconds to the current time. The default is 0.
VARIABLE NAME	(Required) Name of variable where the value is stored.

Example

```
<TAG:GetTime Secondoffset="3600" Variable="Time">
```

GetTotal

Description

Calculates the total for the specified column for all selected rows and assigns the value to a variable.

Usage

Use GetTotal to calculate a column total and display the total in your report.

Syntax

```
<TAG:GetTotal AppletName="APPLET NAME" FieldName="FIELD NAME" Query="QUERY STRING" Variable="VARIABLE NAME">
```

Parameter	Description
TAG:GetTotal	(Required) Required tag indicator.
APPLET NAME	(Required) Name of the applet.

Parameter	Description
FIELD NAME	(Required) Name of the field or column. Specify a field or column with numeric data. If you specify a field with non-numeric data, a 0 is assigned to the variable.
QUERY STRING	(Optional) Search specification for the rows to be included in the total. If not specified, the current search specification is used. The syntax for the query string is: Field Name Query Statement. You may specify one or more query strings separated by a vertical bar (). For example, Query="Name LIKE 'Sieb*'" "Location LIKE 'H*'"
VARIABLE NAME	(Required) Name of variable where the value is stored.

Example

```
<TAG:GetTotal AppletName= "CS HH Product Bucket List Applet" Fieldname="Quantity"
Variable="ProdBucketListTotal">
```

Header

Description

Adds header information such as page numbers, the current date, and the current time.

Usage

You may always want the current date and time to appear on your invoices. If so, you may include this information in a Header tag.

The Header tag may be specified anywhere in the template file; however, it always appears at the very top of your document. Only one Header tag is applied to the document. If you have multiple Header tags in the file, only the last Header tag is used; any other Header tags are ignored.

If you include a Header tag in your template, then you must set TopMargin in setup.ini to a minimum of 20.

The header has three sections, Left, Center, and Right, which are used to position the information in the header. The Left parameter aligns the text with the left margin, and the Right parameter right aligns the text with the right margin. The Center parameter centers the text in the header.

The text in the header is formatted in 10 point, Helvetica font. If Helvetica is not available on your system, the default font is used. You cannot customize text formatting of the Header tag. The Format tag does not affect the format of the header.

Syntax

<TAG:Header Left="DATA" Center="DATA" Right="DATA">

Parameter	Description								
TAG:Header	(Required) Header tag indicator.								
DATA	(Optional) Static text or one of the following data tags:								
	<table border="1"> <thead> <tr> <th>Data tag</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td><page></td> <td>Page number</td> </tr> <tr> <td><date></td> <td>Date of the printing</td> </tr> <tr> <td><time></td> <td>Time of the printing</td> </tr> </tbody> </table>	Data tag	Description	<page>	Page number	<date>	Date of the printing	<time>	Time of the printing
Data tag	Description								
<page>	Page number								
<date>	Date of the printing								
<time>	Time of the printing								

Example

<TAG:Header Center="Company Confidential">

Page Break

Description

Forces text that follows the tag to appear on the next page.

Usage

Use this for multipage documents or forms.

Syntax

<TAG:PageBreak>

Parameter	Description
TAG:PageBreak	(Required) Page break tag indicator.

Example

<TAG:PageBreak>

Picture

Description

Specifies graphic files included in the print template.

Usage

Use to add graphic images, such as a company logo, to your documents.

The supported file formats are BMP and JPG.

Graphics files are located in the \Program Files\Siebel Handheld\templates directory on the handheld device. Specify the full path name of the file for the Name parameter.

Scaling or graphics operations, such as inverse image, are not supported.

The Alignment and Position parameters are used together to place the graphic. Alignment specifies the left edge, the center, or the right edge of the graphic. Position is distance, specified in millimeters, from the left edge of the paper.

- If Alignment = "Left" and Position="30", then the left edge of the graphic is set 30 millimeters from the left edge of the paper.
- If Alignment = "Center" and Position = "30", the center of the graphic is set 30 millimeters from the left edge of the paper.
- If Alignment = "Right" and Position = "30", the right edge of the graphic is set 30 millimeters from the left edge of the paper.

If Position is not specified, it defaults to 0. Depending on the Alignment setting, the graphic is left-aligned (Alignment = "Left"), the graphic is right-aligned (Alignment = "Right"), or the graphic is centered (Alignment = "Center")

Syntax

```
<TAG:Picture Name="FILE NAME" Alignment="ALIGNMENT" Position="POSITION">
```

Parameter	Description
TAG:Picture	(Required) Picture tag indicator.
FILE NAME	(Required) Specifies the full path and name of the graphics file.
ALIGNMENT	(Optional) Specifies the left edge, the center, or the right edge of the graphic. Used with the Position parameter to specify the horizontal position of the graphic. Valid values are LEFT (default), CENTER, and RIGHT.
POSITION	(Optional) Specified in millimeters, it is the distance from the left edge of the paper. Used with the Alignment parameter to specify the horizontal position of the graphic. The default is 0.

Example

```
<TAG:Picture Name="\Program Files\Siebel Handheld\templates\logo.bmp" Alignment="Right" Position="88">
```

SetVariable

Description

Sets a value to a variable.

Usage

Use SetVariable to assign a value to a variable. You can then print the value by specifying the variable in the Cell tag.

Syntax

```
<TAG:SetVariable Name="VALUE" Variable="VARIABLE NAME">
```

Parameter	Description
TAG:SetVariable	(Required) Required tag indicator.
VALUE	(Required) A value.
VARIABLE NAME	(Required) Name of variable where the value is stored.

Example

```
<TAG:SetVariable="100" Variable="TotalQuantity">
```

Static Text

You may add static text anywhere in your template by using the current Format settings. The text goes across the entire page width. If it exceeds the width of the page, it wraps to the next line.

Example

This quote is valid for 60 days from the date on this quotation.

Title

Description

Name used to identify the template.

Usage

The Title tag is a required tag in your print template file.

When you print your document, this title appears in the print job list. This title does not appear on the document that is printed. Use static text to add the document title to your template.

Syntax

<TAG:Title Title="TITLE">

Parameter	Description
TAG:Title	(Required) Title tag indicator.
TITLE	(Required) Title text. May be between 1–255 characters.

Example

<TAG:Title Title="Quotation">

Using Variables in Print Templates

The following example shows how to use variables in a print template.

```
<TAG:Title Title="Inventory Report">
<REM: *****Variable Assignment Examples*****>
<TAG:SetVariable name="THIS IS VARIABLE" variable="VarStr">
<TAG:GetRegistry name="InstallDir" variable="VarReg">
<TAG:GetDate dayoffset="10" variable="VarDate">
<TAG:GetDate longformat="TRUE" variable="VarLongDate">
<TAG:GetTime secondoffset="-3600" variable="VarTime">
<TAG:GetTotal appletname="CS HH Product Bucket List Applet" fieldname="Quantity"
variable="VarTotal">
<TAG:GetTotal appletname="CS HH Product Bucket List Applet" fieldname="Quantity"
query="Status|Good" variable="VarGoodTotal">
<TAG:GetTotal appletname="CS HH Product Bucket List Applet" fieldname="Quantity"
query="Status|Defective" variable="VarDefectiveTotal">
<TAG:GetField appletname="CS HH Product Bucket List Applet" fieldname="Quantity"
variable="VarQuantityField">
<TAG:GetCount appletname="CS HH Product Bucket List Applet" query="Status|Good"
variable="VarGoodCount">
<TAG:GetCount appletname="CS HH Product Bucket List Applet" query="Status|Defective"
variable="VarDefectiveCount">
<REM: *****Variable Assignment Examples End*****>
<REM: Inventory Print Template. This template includes 3 applets. The ENU template>
<TAG:Format Face="Helvetica" Size="16" Align="Center">
[Distributor Name
Street Address
City, Country Postal Code
Phone Number Fax Number]
```

```
<TAG:Format Face="Helvetica" Size="20" Bold="TRUE" Align="Center">
Inventory Report
<TAG:Format Face="Helvetica" Size="8" >
<TAG:Applet Name="CS HH Inv Loc Print Applet" Caption="TRUE" Wrap="TRUE">
<TAG:Applet Name="CS HH Product Bucket List Applet" Line="FALSE" Headerdivider="TRUE"
Recorddivider="FALSE" Wrap="TRUE">

<REM: *****Variable Usage Example*****>

<TAG:Divider weight="3" startat="20" endat="80">
<TAG:Cell startat="0" endat="50" name="TOTAL:" Align="RIGHT">
<TAG:Cell startat="50" endat="100" variable="VarTotal" Align="RIGHT">
<TAG:EndOfLine>
<TAG:Cell startat="0" endat="50" name="TOTAL Defective:" Align="RIGHT">
<TAG:Cell startat="50" endat="100" variable="VarDefectiveTotal" Align="RIGHT">
<TAG:EndOfLine>

<TAG:Cell startat="0" endat="50" name="TOTAL Good:" Align="RIGHT">
<TAG:Cell startat="50" endat="100" variable="VarGoodTotal" Align="RIGHT">
<TAG:EndOfLine>

<TAG:Cell startat="0" endat="50" name="Defective Count:" Align="RIGHT">
<TAG:Cell startat="50" endat="100" variable="VarDefectiveCount" Align="RIGHT">
<TAG:EndOfLine>

<TAG:Cell startat="0" endat="50" name="Good Count:" Align="RIGHT">
<TAG:Cell startat="50" endat="100" variable="VarGoodCount" Align="RIGHT">
<TAG:EndOfLine>

<TAG:Cell startat="50" endat="100" variable="VarReg">
<TAG:EndOfLine>

<TAG:Cell startat="50" endat="100" variable="VarStr">
<TAG:EndOfLine>

<TAG:Cell startat="0" endat="30" variable="VarDate">
<TAG:Cell startat="30" endat="70" variable="VarLongDate">
<TAG:Cell startat="70" endat="100" variable="VarTime">
<TAG:EndOfLine>

<REM: *****Variable Usage Example End*****>

<TAG:Divider weight="2">
<TAG:Format Face="Helvetica" Size="12" Align="LEFT">
Warehouse Signature
<TAG:Divider weight="2">
<TAG:Format Face="Helvetica" Size="12" Align="RIGHT">

Rep Signature
```

F

Print Configuration Settings

You configure printing attributes in the setup.ini file. This appendix describes the printing parameters for Siebel application developers and application administrators.

Overview of Siebel Handheld Print Configuration Settings

The administrator sets up the default printer setting in the setup.ini file located in the setup directory.

There are a number of parameters to specify printing on the handheld. The parameters specify the following:

- Printer attributes (printer model, port, baud rate, and printer handshake).
- Printing attributes (portrait or landscape orientation, print density and quality, use of compression techniques, and advancing continuous-feed paper).
- Dimensions of the paper (U.S. or European standard paper sizes or custom-size paper).
- Margin settings of the pages (left, right, top, and bottom margins).

These parameters are specified in the [Printing] section of the setup.ini file located in the setup directory. The file contains default settings for all the printing parameters. Review the settings in the file to verify that these settings will work for your printing environment. If necessary, edit the settings as required. You may use any text editor to edit the file.

See [Appendix E](#) for a list of the printing parameters and valid values.

The parameters are set using the following syntax:

```
PARAMETER_NAME = VALUE
```

For example: PrinterType = 1

The parameters are listed below in alphabetical order by the parameter name.

MarginBottom

Use the MarginBottom parameter to specify the dimensions of the bottom margin of your page. Specify the margin in millimeters using a whole number; decimal fractions are not valid. The default is 5 millimeters.

The data specified in the Footer tag of the print template is printed in the margin specified by MarginBottom. Therefore, if the print template includes a Footer tag, you must specify a wide enough bottom margin to accommodate the footer. MarginBottom should be set to a minimum of 20 millimeters. For more information, see ["Footer" on page 161](#).

MarginLeft

Use the MarginLeft parameter to specify the width of the left margin of your page. Specify the margin in millimeters using a whole number; decimal fractions are not valid. The default is 5 millimeters.

MarginRight

Use the MarginRight parameter to specify the width of the right margin of your page. Specify the margin in millimeters using a whole number; decimal fractions are not valid. The default is 5 millimeters.

MarginTop

Use the MarginTop parameter to specify the dimensions of the top margin of your page. Specify the margin in millimeters using a whole number; decimal fractions are not valid. The default is 5 millimeters.

The data specified in the Header tag of the print template is printed in the margin specified by MarginTop. Therefore, if the print template includes a Header tag, you must specify a wide enough top margin to accommodate the footer. MarginTop should be set to a minimum of 20 millimeters. For more information, see ["Header" on page 167](#).

PaperHeight

If the paper that your printer uses is not one of the supported standard sizes, then set PaperSize to 5 (custom paper dimensions). Then, specify the height of the paper, in millimeters, using the PaperHeight parameter. You must use a whole number; decimal fractions are not valid. The default is 280 millimeters. If you specify a value of 1–4 for PaperSize, the PaperHeight parameter is ignored.

Use the PaperWidth parameter to specify the width of the paper.

PaperSize

Specify one of the standard paper sizes or specify a custom paper size. (See [Table 36](#).) If you specify custom paper size (5), you must also specify the PaperWidth and PaperHeight parameters. The default is custom paper dimensions.

See also PaperWidth and PaperHeight.

Table 36. Paper Dimensions

Value	Description
1	Letter size (8.5" x 11.5")
2	A4 (210 mm x 297 mm)
3	B5 (176 mm x 250 mm)
4	Legal size (8.5" x 14")
5 (default)	Custom paper dimensions (Specify PaperWidth and PaperHeight parameters.)

PaperWidth

If the paper that your printer is printing to is not one of the supported standard sizes, then set PaperSize to 5 (custom paper dimensions). Then, you must specify the width measurement of the paper, in millimeters, using the PaperWidth parameter. You must use a whole number; decimal fractions are not valid. The default is 5 millimeters. If you specify a value of 1–4 for PaperSize, the PaperWidth parameter is ignored.

Use the PaperHeight parameter to specify the length of the paper.

PrinterBaudrate

Use PrinterBaudrate to specify the speed of the data transmission for the printer. (See [Table 37.](#))

Table 37. Printer Baud Rate

Value	Description
0	Always use 0 for LPT or Network printer ports or for COM ports that communicate with the printer at 4800 baud
1 (default)	9600 baud
2	19200 baud
3	38400 baud
4	57600 baud
5	115200 baud

PrinterCompressed

Use PrinterCompressed to specify the data compression mode. (See [Table 38.](#)) For the printers supported in this release, always set PrinterCompressed to 1.

Table 38. Data Compression

Value	Description
0	No compression techniques used
1 (default)	Use any known compression

PrinterDensity

Use the PrinterDensity parameter to get a lighter or darker output from the printer. Start with the default setting, 2, which corresponds to the printer manufacturer’s default. As you get feedback from the field, you may need to adjust this setting.

The valid values are 0–4 where 0 is the lightest print density, 4 is the heaviest print density, and 2 is average print density.

PrinterDither

Use to specify the method by which different colors are represented. (See [Table 39.](#)) For the printers supported in this release, PrinterDither should always be set to 0.

Table 39. Print Dithering

Value	Description
0 (default)	Use color diffusion
1	Use dithering

PrinterDraftMode

Use PrinterDraftMode to specify the quality of the printing. (See [Table 40.](#)) For the printers supported in this release, PrinterDraftMode should always be set to 0.

Table 40. Print Quality

Value	Description
0 (default)	Use the highest quality printing
1	Use a lower quality printing if available

PrinterFormFeed

Use PrinterFormFeed to specify how paper advances to the next page. (See [Table 41.](#)) If using sheets of paper, set PrinterFormFeed to 0.

Specify 1 or 2 for continuous-feed paper:

- Set PrinterFormFeed to 1 if you do not need to conserve paper or if you want pages of uniform length. The printer scrolls to the length specified by the PageHeight parameter and trims the page there.
- Set PrinterFormFeed to 2 to conserve paper or if it does not matter if your pages are of varying length. In this case, the printer scrolls 25 millimeters beyond the last printed line and trims the page there. The scroll distance, 25 mm, is not customizable.

For both values, 1 and 2, the page length never exceeds PageHeight.

Table 41. Printer Form Feed

Value	Description
0 (default)	Printer sends a form feed command to the printer at the end of each page. Use this setting for sheet paper.
1	Printer scrolls the page to the length specified by the PaperHeight parameter.
2	Printer scrolls the page 25 millimeters past the last printed line of the page.

PrinterHandshake

Use PrinterHandshake to define the serial port handshake. (See [Table 42.](#)) The PrinterHandshake parameter applies only when the printer port is a Com1 or Com2 port. If PrinterPort is set to Com1 or Com2, then set PrinterHandshake to 1.

Table 42. Printer Handshake

Value	Description
0	Uses Xon/Xoff
1 (default)	Uses hardware control lines
2	No handshaking of serial port

PrinterOrientation

Specify whether the paper is to be oriented vertically (portrait) or horizontally (landscape). (See [Table 43.](#)) Not all printers can print in landscape orientation. Therefore, you will need to check the specifications for your printer.

Table 43. Paper Orientation

Value	Description
1 (default)	Portrait (vertical)
2	Landscape (horizontal)

PrinterPort

Specify the port to which the printer is connected with the PrinterPort parameter. (See [Table 44.](#)) If PrinterPort is an LPT port or a network path (2 or 9), then the PrinterBaudrate must be set to 0.

Table 44. Printer Port

Value	Description
0	Com1: serial port
1	Com2: serial port
2	LPT: parallel port
3 (default)	IR Infrared port
4	Com3: serial port

Table 44. Printer Port

Value	Description
5	Com4: serial port
6	Com5: serial port
7	Com6: serial port
8	Print to file OUTPUT.PRN
9	Print to network address
10	Bluetooth BlueCard solution by Wireless Solutions
11	Socket PNC Bluetooth card support
12	Bluetooth BlueCard solution by Anycor
13	Com7: serial port
14	Com8: serial port

PrinterType

Specify the type of printer using the PrinterType parameter. See [Table 45](#) for the list of supported printers.

Table 45. Printer Type

Value	Description
6	Pentax PocketJet 200
14 (default)	O'Neil microFlash2i and microFlash4t printers
108	O'Neil microFlash8i printer

Default Printing Settings

The following are the printing parameters from the setup.ini file. The values shown are the default settings.

[Printing]

```
PrinterType= 14
PrinterPort= 3
PrinterBaudrate= 1
PrinterHandshake= 1
PrinterOrientation= 1
PrinterDensity= 2
PrinterCompressed= 1
PrinterDither= 0
```

PrinterDraftMode= 0
PrinterFormFeed= 0
PaperSize= 5
PaperWidth= 115
PaperHeight= 280
MarginLeft= 5
MarginRight= 5
MarginTop= 5
MarginBottom= 5

Index

- A**
- accounts, managing**
 - about and Accounts screen's views 111
 - account addresses, adding 112
 - account information, adding 112
 - activities, associating with accounts 113
 - creating accounts 112
 - opportunities, adding to an accounts 114
 - scenario 112
- activities**
 - about 119
 - associating with accounts 113
 - contact participants, specifying 121
 - contacts, associating with activities 120
 - creating activities 119
 - delegating activities 119
 - employee participants, specifying 121
 - general activities, adding using the Calendar view 120
- applet classes, list of** 147
- Applet print tag** 156
- applets**
 - default behavior, overriding 23
 - form applets, designing 34
 - list applets, designing 35
 - multiple-applet views, toggling between 22
 - print applets, designing 34
 - Print buttons, configuring 35
 - printing, configuring 35
 - screen allocation 22
 - toggling between 94
 - URLs in applet fields 95
- application memory, increasing** 107
- application-level menu**
 - about 92
- architecture**
 - five layers described 17
- asterisk (*), meaning in forms and applets** 25
- Auto Order**
 - creating order from quote 126
 - Order Entry - Line Items view fields 151
 - Order Entry - Order business component fields 152
 - Service Products copied fields 152
- auto pop-up list**
 - using, about 26
- Auto Quote**
 - about using 123
 - AutoQuote method values 150
 - creating a quote 124
 - quote items, adding 124
 - quote items, deleting 125
- automatic backup**
 - after synchronization 100
- B**
- Back button, about** 95
- backing up data**
 - about 100
 - automatic backup after synchronization 100
 - database backup parameters, editing 71
 - database backup, about enabling 70
 - database backup, setting up 71
 - external media, backing up to 71
 - restoring data from a backup 101
 - restoring from a backup, about 72
 - troubleshooting 131
- barcode scanning, preparing handheld application for** 89
- Billing field, about supporting** 128
- business component classes**
 - list of component classes 146
- business components**
 - list of supported components 145
- business object declarations, setting PDQ examples** 58
- business object filters**
 - configuring 36
- buttons**
 - about and behavior 27
- C**
- calendar**
 - customizing, about 99
 - viewing 99
- Calendar view**
 - using to add general activities 120
- Cell print tag** 157
- client**
 - installation, troubleshooting backup and

- restore 131
- performance troubleshooting 137
- columns, working with** 96
- Comment print tag** 159
- CompactFlash card**
 - backing up to, about 71
 - handheld application, about installing from 74
 - installation, setting up on 72
 - stand-alone installer, creating 74
- Companion Sync**
 - administration of 55
- Companion Synchronization**
 - checklist, using to troubleshoot 132
 - handheld application, using to install 86
 - handheld, using with 102
 - log files, using for troubleshooting 134
 - note, synchronizing to the Siebel Server 63
 - using to deploy patches 76
- companion synchronization server, described** 14
- configuration file**
 - See also* configuring
 - default views, specifying 42
 - directives, about 57
- configuring**
 - Siebel Handheld client 15
 - Web Client and Handheld Client, differences in configuring 18
- conflicts**
 - See* synchronization, conflict handling and recover
- Contacts screen views**
 - accessing to manage contacts 109
- contacts, managing**
 - about 109
 - activities, associating with contacts 120
 - adding contacts 110
 - contact participants, specifying 121
 - Contacts screen views, accessing to manage contacts 109
 - opportunities, associating contacts with 111
 - opportunity, associating with a contact 117
 - scenario 110
- customer relationships, managing**
 - about 118
 - activities, about 119
 - activities, delegating 119
 - activity, creating 119
 - contact participants, specifying 121
 - contacts, associating with activities 120

- employee participants, specifying 121
- general activities, adding using the Calendar view 120
- scenario 119

D**data**

- automatic backup after synchronization 100
- backing up, about 100
- columns, working with 96
- Companion Synchronization, synchronizing handheld client for 103
- Companion Synchronization, using with handheld 102
- Direct Server Synchronization, using with handheld client 104
- entering, about 96
- exporting 98
- Find, about using 97
- queries, about 97
- queries, creating 98
- queries, executing 98
- queries, refining 98
- restoring data from a backup 101
- Siebel Handheld Synchronization, using with handheld client 102
- synchronizing data, about 102

data filtering

- developing data filters, steps 51
- pick applet, data filtering for 56
- Sales Handheld PDQ filters 52

database backups

- about 100
- automatic backup after synchronization 100
- database backup parameters. editing 71
- enabling, about 70
- restoring data from a backup 101
- setting up database backups 71
- troubleshooting 131

DDvP

- See* Direct Server Sync via Proxy

default sync filters, about 52**deleting**

- quote line items 125

Direct Server Sync via Proxy, about 15**Direct Server Synchronization**

- See also* Direct Server Synchronization (DDS) infrastructure
- about 56
- about and diagram 15
- checklist, using to troubleshoot 132

- described 14
 - handheld application, using to install 87
 - handheld client, using with 104
 - log files, using for troubleshooting 133
 - network performance,
 - troubleshooting 138
 - patches, using to deploy 75
 - server performance, troubleshooting 137
 - Direct Server Synchronization (DDS) infrastructure**
 - DDS components, about installing 64
 - DSS object manager configuration file,
 - editing 65
 - hardware and network configuration,
 - recommended 63
 - multiple synchronization servers, using 67
 - planning, about 62
 - server logging levels, configuring 66
 - server process management,
 - optimizing 67
 - server topology overview 63
 - Siebel Server installer, using 64
 - synchronization performance and scalability,
 - about 67
 - synchronization security, about 67
 - direct synchronization server,**
 - described 14
 - Divider print tag** 159
 - documents, defining** 34
 - downloading patches** 77
 - drilldowns, about** 31
 - DSS object manager configuration file,**
 - editing 65
 - dynamic hyperlink, about** 31
- E**
- ellipsis, and expandable fields** 94
 - employee participants, specifying** 121
 - end user error messages**
 - See troubleshooting
 - EndofLine print tag** 160
 - error data, accessing** 84
 - error messages**
 - See troubleshooting
 - errors**
 - general synchronization errors 105
 - synchronization transaction conflicts 106
 - expenses, tracking**
 - detailed line items, adding 128
 - expense report, creating 128
 - expense report, submitting 129
 - procedures, about 128
 - exporting data** 98
- extended insert processing**
 - about and synchronization 82
 - enabling 82
 - extended pick processing**
 - about and synchronization 79
 - enabling 80
 - external media**
 - backing up to 71
 - handheld application, about installing
 - from 74
 - stand-alone installer, creating 74
- F**
- features, new** 11
 - Find**
 - about using 97
 - Footer print tag** 161
 - form applets, configuring**
 - about 25
 - designing, about 34
 - group boxes, about 26
 - labels, about 26
 - layout sequence 25
 - Format print tag** 162
 - Forward button, about** 95
- G**
- general sync filters, about** 52
 - GetCount print tag** 163
 - GetDate print tag** 163
 - GetField print tag** 164
 - GetRegistry print tag** 165
 - GetTime print tag** 166
 - GetTotal print tag** 166
 - global user properties, list of** 149
 - GotoView method, using** 23
 - group boxes, about configuring guidelines**
 - Siebel Handheld client screen, about
 - designing for 21
 - Siebel Handheld client, configuration
 - guidelines 21
 - Siebel Handheld, recommended configuration
 - guidelines 32
- H**
- handheld device logs**
 - list of log files 134
 - synchronization errors, logging 135
 - handheld interface**
 - See interface
 - Header print tag** 167
 - help**

- Siebel Expert Services, about using 139
 - Siebel Professional Services, about using 139
 - History arrows, about** 95
 - Home Page applet, using** 26
 - Hotel expense tax itemization**
 - about supporting 129
 - hyperlinks, about** 31
- I**
- installing**
 - barcode scanning, preparing handheld application for 89
 - CompactFlash card. setting up installation on 72
 - Companion Sync, using to deploy patches 76
 - database backup parameters, editing 71
 - Direct Server Sync, using to deploy patches 75
 - Direct Server Sync, using to install handheld application 87
 - external media, about installing from 74
 - external media, backing up to 71
 - install directory, changing 74
 - patches, about distributing 74
 - patches, downloading 77
 - print templates in the Install directory 72
 - process of installation 68
 - read-only files, changing attributes 77
 - reinstalling the handheld application 88
 - restart parameter, setting 73
 - restoring from a backup, about 72
 - setup.ini file, editing 68
 - software on handheld. about 85
 - stand-alone installer, creating 74
 - SyncURL, changing 73
 - uninstalling handheld application 89
 - upgrade kits, creating to remotely deploy patch files 77
 - upgrading the handheld application 88
 - user database backup, about enabling 70
 - user database backup, setting up 71
 - using Companion Sync users to install handheld application 86
 - Integrated Sync**
 - handheld client, synchronizing for Companion Sync 103
 - synchronizing data, and 102
 - interface**
 - application-level menu 92
 - components, about and diagram 91
 - expandable fields 94
 - Minimize button 93
 - More Info view, navigation level 94
 - Queries drop-down list 93
 - screens menu, about 92
 - screens menu, navigation level 94
 - Show drop-down list, about 92
 - Show drop-down list, navigation level 94
 - Siebel toolbar, about 93
 - Siebel toolbar, customizing 93
 - status bar 93
 - toggling between applets 94
 - URLs in applet fields 95
- L**
- labels, about configuring** 26
 - list applets, configuring**
 - about 24
 - designing, about 35
 - recommended strategy 24
 - log files**
 - Companion Sync logs, using for troubleshooting 134
 - Direct Server Sync logs, using for troubleshooting 133
 - handheld device logs, using for troubleshooting 134
- M**
- MarginBottom parameter** 173
 - MarginLeft parameter** 174
 - MarginRight parameter** 174
 - MarginTop parameter** 174
 - Maximize Minimize Applet button, about** 93
 - media**
 - external media, backing up to 71
 - handheld application, about installing from external media 74
 - stand-alone installer, creating 74
 - memory, increasing** 107
 - menu bar, about** 30
 - methods**
 - AutoOrder method 151
 - AutoQuote method fields 151
 - AutoQuote method values 150
 - Mileage expense type**
 - about supporting 129
 - Minimize button, about** 93
 - More Info View**
 - navigation level 94
 - multiple synchronization servers**
 - about using 67
 - Multi-Value Group applet, support of** 19

N

- naming conventions, about** 22
- network performance, about** 138
- new features** 11

O**opportunities**

- adding to an account 114
- contact, associating with an opportunity 117
- contacts, associating with an existing opportunity 111
- creating opportunities 115
- defined and examples 114
- opportunity quotes, about 118
- product, associating with an opportunity 117
- sales methods, about 116
- scenario 115

orders, managing

- about 126
- Auto Order, creating orders from quote 126
- manually create an order 127
- order line items, adding 127
- terms and totals, adding 127

P

- Page Break print tag** 168
- PaperHeight parameter** 174
- PaperSize parameter** 174
- PaperWidth parameter** 175
- parent form applet, about** 22
- PatchAgent, about** 74
- patches**
 - Companion Sync, using to deploy patches 76
 - Direct Server Sync, using to deploy patches 75
 - distributing, about 74
 - downloading 77
 - read-only files, changing attributes 77
 - synchronizing data, and 102
 - upgrade kits, creating to remotely deploy patch files 77
- PDQ filters, administration**
 - Companion Sync, about 55
 - Direct Server Sync mode, about 56
- PDQs**
 - Queries drop-down list, and 93
- performance**
 - application memory, increasing 107
 - client performance, about 137

- handheld screen, about designing for improving by identifying user activities 21
- improving performance, about 106
- network performance, about 138
- server performance, about 137
- SQLTrace and synchronization 135

pick applets, data filtering for

- about 56
- business object declarations, setting examples 58
- configuration file directives 57
- Popup Visibility Type setting, overriding visibility, designating 60

Picture print tag 168**pop-up lists**

- auto pop-up lists, about using 26

Popup Visibility Type setting, overriding 60**predefined queries**

- Queries drop-down list, and 93

Predefined Queries (PDQs)

- general and default PDQ filters, described 52

preferences

- setting user preferences 100

print applets

- designing, about 34

Print buttons, configuring 35**print tagging language**

- See print templates

print templates

- Applet print tag 156
- Cell print tag 157
- Comment print tag 159
- creating print templates 36
- Divider print tag 159
- EndofLine print tag 160
- Footer print tag 161
- Format print tag 162
- GetCount print tag 163
- GetDate print tag 163
- GetField print tag 164
- GetRegistry print tag 165
- GetTime print tag 166
- GetTotal print tag 166
- Header print tag 167
- Install directory. installing in Page Break print tag 168
- Picture print tag 168
- print template file, creating overview 155
- SetVariable print tag 170
- Static Text print tag 170
- Title print tag 170
- variables, example using in template 171

- views, associated with 23
 - PrinterBaudrate parameter** 175
 - PrinterCompressed parameter** 176
 - PrinterDensity parameter** 176
 - PrinterDither parameter** 176
 - PrinterDraftMode parameter** 177
 - PrinterFormFeed parameter** 177
 - PrinterHandshake parameter** 178
 - PrinterOrientation parameter** 178
 - PrinterPort parameter** 178
 - PrinterType parameter** 179
 - printing**
 - handheld application, printing with 98
 - quotes 125
 - printing, configuration settings**
 - default printing settings, list of 179
 - MarginBottom parameter 173
 - MarginLeft parameter 174
 - MarginRight parameter 174
 - MarginTop parameter 174
 - PaperHeight parameter 174
 - PaperSize parameter 174
 - PaperWidth parameter 175
 - parameters and syntax 173
 - PrinterBaudrate parameter 175
 - PrinterCompressed parameter 176
 - PrinterDensity parameter 176
 - PrinterDither parameter 176
 - PrinterDraftMode parameter 177
 - PrinterFormFeed parameter 177
 - PrinterHandshake parameter 178
 - PrinterOrientation parameter 178
 - PrinterPort parameter 178
 - PrinterType parameter 179
 - printing, configuring**
 - about 33
 - applet, configuring for printing 35
 - documents, defining 34
 - form applets, designing 34
 - list applets, designing 35
 - print applets, designing 34
 - Print buttons, configuring 35
 - print templates, creating 36
 - products**
 - associating with an opportunity 117
 - projects**
 - naming conventions, and 22
- Q**
- queries**
 - about using 97
 - creating a query 98
 - executing 98
 - refining 98
 - Queries drop down list, about** 93
 - quotes, developing**
 - about 122
 - Auto Order, creating from quote 126
 - Auto Quote, about using 123
 - Auto Quote, creating a quote 124
 - creating quotes 122
 - developing quotes scenario 122
 - opportunity quotes, about 118
 - printing quotes 125
 - quote item, adding 124
 - quote item, deleting 125
- R**
- read-only files**
 - changing attributes for upgrade kits 77
 - record navigation buttons** 95
 - records, navigating a list of**
 - about 95
 - Back and Forward buttons 95
 - History arrows 95
 - record navigation buttons 95
 - reinstalling the handheld application** 88
 - reports**
 - expense report, creating 128
 - expense report, submitting 129
 - views, associated with 23
 - repository**
 - compiling 33
 - restart parameter, setting** 73
 - restoring data**
 - from a backup 101
 - troubleshooting 131
- S**
- Sales Handheld PDQ filters**
 - about 52
 - sales methods, about** 116
 - screens**
 - designing screens for Siebel Handheld,
 - about 22
 - screen allocation 22
 - views, list of 141
 - screens menu**
 - about 92
 - navigation level 94
 - scripting**
 - deactivating scripts, about 61
 - user interface methods, calls to 61
 - server installation**
 - Direct Server Synchronization (DDS), about
 - installing 64

- Direct Server Synchronization (DDS), using
 - Siebel Server installer 64
- DSS object manager configuration file,
 - editing 65
- hardware and network configuration,
 - recommended 63
- multiple synchronization servers, using 67
- planning for, about 62
- server logging levels, configuring 66
- server process management,
 - optimizing 67
- server topology overview 63
- synchronization performance and scalability,
 - about 67
- synchronization security, about 67
- server logging levels, configuring** 66
- server performance, troubleshooting** 137
- server process management, optimizing** 67
- ServiceCE Generic, about** 30
- setup.ini file, editing** 68
- SetVariable print tag** 170
- Shipping field, about supporting** 128
- Show drop-down list**
 - about 92
 - navigation level 94
- Siebel Anywhere**
 - using to create upgrade kits 77
- Siebel eScript**
 - issues and validation 61
- Siebel Expert Services**
 - about using 139
- Siebel Handheld Client**
 - application memory, increasing 107
 - auto-pop-up list, using 26
 - compiling the repository 33
 - configuration guidelines 21
 - configuration guidelines, recommended 32
 - Direct Server Synchronization, using with
 - handheld client 104
 - form applets, about configuring 25
 - general synchronization errors 105
 - handheld screen, about designing for 21
 - Home page applet, about 26
 - hyperlinks, about 31
 - improving performance, about 106
 - list applets, configuring 24
 - menu bar, about 30
 - Multi-Value Group applet, support of 19
 - printing, configuring 33
 - process of configuring 17
 - scripting, about 61
 - Siebel Web Client, differences in
 - configuring 18
 - status bar, about 31
 - synchronization conflicts, preventing 32
 - synchronization transaction conflicts 106
 - synchronizing for Companion Synch 103
 - testing the handheld application 38
 - toolbars, about 30
 - unsupported functions 19
 - user functionality, defining 20
 - user interface elements, about
 - configuring 24
- Siebel Handheld projects**
 - about creating and naming conventions 22
- Siebel Handheld Synchronization**
 - application memory, increasing 107
 - Companion Synchronization, using with
 - handheld 102
 - Direct Server Synchronization, using with
 - handheld client 104
 - general synchronization errors 105
 - handheld client, synchronizing for Companion Synch 103
 - handheld client, using 102
 - improving performance, about 106
 - synchronization transaction conflicts 106
- Siebel Handheld upgrade kit**
 - creating upgrade kit 77
 - read-only files, changing attributes 77
- Siebel Mobile Web Client**
 - Companion Sync, using to deploy
 - patches 76
 - installation, about 68
 - read-only files, changing attributes for
 - upgrade kits 77
 - upgrade kit, creating 77
- Siebel Professional Services**
 - about using 139
- Siebel Server installer**
 - DSS component, using to install 64
 - DSS object manager configuration file,
 - editing 65
 - server logging levels, configuring 66
 - server process management,
 - optimizing 67
- Siebel toolbar**
 - about 93
 - customizing 93
- Siebel Visual Basic (VB)**
 - issues and validation 61
- Siebel Web Client**
 - Multi-Value Group applet, support of 19
 - scripting, issues and validation 61
 - Siebel Handheld client, differences in
 - configuring 18
 - unsupported functions 19

signature capture

- enabling, about and screen capture buttons 36
- signature capture applet control user properties 37

software

- about installing on handheld 85

SQLTrace, enabling 135**.SRF file**

- compiling repository file 33

stand-alone installer, creating 74**Static Text print tag** 170**status bar**

- application window, appears at bottom of 93
- toolbar, located above 31

submitting

- expense report 129

synchronization

- Direct Server Sync via Proxy, about 15
- Direct Server Sync, about and diagram 15
- methods and architecture 14
- overview 14
- servers, types of 14

synchronization, conflict handling and recovery

- about 79
- error data, accessing 84
- extended insert pick processing, about 82
- extended insert pick processing, enabling 82
- extended pick processing, about 79
- extended pick processing, enabling 80

synchronizing

- application memory, increasing 107
- automatic backup after synchronization 100
- Companion Synchronization, using with handheld 102
- data, about 102
- Direct Server Synchronization, using with handheld client 104
- general synchronization errors 105
- handheld client, synchronizing for Companion Sync 103
- handheld synchronization errors, logging 135
- improving performance, about 106
- multiple synchronization servers, using 67
- performance and scalability, about 67
- resynchronization problems, troubleshooting 133
- security, about 67

Siebel Handheld Synchronization, using with handheld client 102

synchronization conflicts, preventing 32

transaction conflicts 106

troubleshooting, about problems caused by 132

SyncURL, changing 73**T****technical support**

Siebel Expert Services, about using 139

Siebel Professional Services, about using 139

templates

- print templates, creating 36
- print templates, views associated with 23

terms, adding to order line items 127**testing the handheld application** 38**timeout parameter**

Windows 2000, changing on 136

Windows NT, changing on 136

Title print tag 170**tooggling between applets** 94**toolbars**

- about 93
- configuring 31
- customizing 93
- toolbar functions 30

totals, adding to order line items 127**troubleshooting**

- client installation, backup, and restore 131
- client performance, about 137
- Companion Sync checklist, using 132
- Companion Sync log files 134
- Direct Server Sync checklist, using 132
- Direct Server Sync log files 133
- general synchronization errors 105
- handheld device logs 134
- network performance, about 138
- resynchronization problems 133
- server performance, about 137
- Siebel Expert Services, about using 139
- Siebel Professional Services, about using 139
- SQLTrace, enabling 135
- synchronization transaction conflicts 106
- synchronization, about problems caused by 132
- timeout parameter, changing on Windows 2000 136
- timeout parameter, changing on Windows NT 136

U**ui**

See user interface elements, configuring

uninstalling the handheld application 89

upgrade kits

creating to remotely deploy patch files 77

read-only files, changing attributes 77

upgrading

handheld application 88

preparing to upgrade 85

URLs

in applet fields, 95

user functionality, defining

about 20

user interface elements, configuring

about 24

auto pop-up lists, about using 26

buttons, about and behavior 27

form applets, about configuring 25

Home Page applet, about 26

hyperlinks, about 31

list applets, about configuring 24

menu bar, about 30

status bar, about using 31

toolbars functions 30

toolbars, about configuring 31

user interface methods

calls to business component script 61

user preferences

about customizing 100

user properties

global user properties, list of 149

list of 149

V**views**

default behavior, overriding 23

designing views for Siebel Handheld,
about 22

drill-down only 23

new views, adding 41

print templates or reports, associated
with 23

visibility, designating 59**W****Web server timeout errors**

timeout parameter, changing on Windows
2000 136

timeout parameter, changing on Windows
NT 136

Windows

timeout parameter, changing on Windows
2000 136

timeout parameter, changing on Windows
NT 136

