
PeopleSoft Enterprise Global Payroll for Hong Kong 9.1 PeopleBook

November 2010

Copyright © 1988, 2010, Oracle and/or its affiliates. All rights reserved.

Trademark Notice

Oracle is a registered trademark of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners.

License Restrictions Warranty/Consequential Damages Disclaimer

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

Warranty Disclaimer

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

Restricted Rights Notice

If this software or related documentation is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, the following notice is applicable:

U.S. GOVERNMENT RIGHTS

Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, duplication, disclosure, modification, and adaptation shall be subject to the restrictions and license terms set forth in the applicable Government contract, and, to the extent applicable by the terms of the Government contract, the additional rights set forth in FAR 52.227-19, Commercial Computer Software License (December 2007). Oracle USA, Inc., 500 Oracle Parkway, Redwood City, CA 94065.

Hazardous Applications Notice

This software is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications which may create a risk of personal injury. If you use this software in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy and other measures to ensure the safe use of this software. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software in dangerous applications.

Third Party Content, Products, and Services Disclaimer

This software and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third party content, products and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third party content, products or services.

Contents

Preface

PeopleSoft Enterprise Global Payroll for Hong Kong Preface	xi
PeopleSoft Products	xi
PeopleSoft Enterprise HRMS Application Fundamentals	xi
Global Payroll Documentation	xi
Global Payroll Application Design	xi
Global Payroll Documentation Structure	xii
Documentation Roadmap	xiii
PeopleBooks and the PeopleSoft Online Library	xiv

Chapter 1

Getting Started with Global Payroll for Hong Kong	1
Global Payroll for Hong Kong Overview	1
Global Payroll for Hong Kong Business Processes	1
Global Payroll for Hong Kong Integrations	2
Global Payroll for Hong Kong Implementation	2

Chapter 2

Understanding Global Payroll for Hong Kong	3
Understanding Global Payroll for Hong Kong	3
Global Payroll for Hong Kong Business Processes	3
Delivered Elements for Hong Kong	5
Creation of Delivered Elements	5
Element Ownership and Maintenance	6
Delivered Elements Naming Convention	8
Element Names	8
Functional Area Codes	11
Element Type Codes (PIN_TYPE)	12
Viewing Delivered Elements	12
Archiving Data for Global Payroll for Hong Kong	13

Chapter 3

Setting Up Global Payroll for Hong Kong	15
Processing Retroactive Payments	15
Entering Additional Information for Other Features	15
Defining Triggers and Segmentation Events for Hong Kong	16
Triggers	16
Segmentation Events	19
Viewing Delivered Elements	19
Identifying Proration Rules	19

Chapter 4

Setting Up Inland Revenue Reports	21
Understanding Setup for Hong Kong Inland Revenue Reporting	21
Viewing Delivered Elements	21
Linking Accumulators with Report Elements	22
Understanding Accumulator Usage in the IR56 Result Table	22
Page Used to Link Accumulators with Report Elements	22
Linking Accumulators with Report Elements	22
Setting Up Employee Departure Details	24
Page Used to Set Up Employee Departure Details	24
Setting Up Employee Departure Details	24
Setting Up Principal Employers for Part-Time Employees	26
Page Used to Set Up Principal Employers for Part-Time Employees	26
Setting Up Employee Housing Quarters Details	26
Pages Used to Set Up Employee Housing Quarters Details	27
Setting Up Employee Housing Quarters Details	27
Setting Up Self-Employment Data	30
Page Used to Set Up Self-Employment Data	30
Setting Up Overseas Concern Details	30
Page Used to Set Up Overseas Concern Details	31
Setting Up IR56B and IR56M Starting Sheet Numbers	31
Page Used to Set Up IR56B and IR56M Starting Sheet Numbers	32
Setting Up Tax Reference Number Details	32
Page Used to Set Up Tax Reference Number Details	33
Setting Up Exchange Rate Details	33
Page Used to Set Up Exchange Rate Details	34

Chapter 5

Setting Up Payslips	35
Understanding Payslips	35
Viewing Delivered Elements	35
Description of Processes in Payslip Job	35
Common Elements Used in This Chapter	36
Creating Payslip Templates	36
Understanding Payslip Templates	36
Pages Used to Create Payslip Templates	37
Setting Up Payslip Templates and Accumulators	37
Setting Up Payslip Earnings and Deductions	40
Setting Up Payslip Absence Details	42
Attaching Payslip Templates to Pay Groups	43
Page Used to Attach Payslip Templates to Pay Groups	43
Attaching Payslip IDs to Pay Groups	43
Creating Payslip Messages	44
Page Used to Create Payslip Messages	44
Creating Payslip Messages	44

Chapter 6

Defining Earnings	47
Understanding Earnings in Hong Kong	48
Viewing Delivered Elements	48
Understanding Subsetting	48
Understanding Delivered Earning Elements	49
Calculating Basic Salary Earnings	51
Calculating Basic Hourly Earnings	52
Calculating Overtime Earnings	52
OT1.5 Calculation Rule	52
OT FIX Calculation Rule	53
Calculating Shift Allowance Earnings	53
Calculating SHNTFIX Earnings	53
Calculating SHNT1.3 Earnings	54
Calculating Typhoon and Black Rain Allowances	54
Calculating TYPHOON Allowances	54
Calculating BLCKRAIN Allowances	54
Calculating Meal Allowances	54
Calculating Meal Reimbursement	55
Calculating Mobile Phone and Pager Allowance	56

Calculating Housing Allowances	56
Working with the ALW BR HOUSING Bracket	56
Calculating Rent Reimbursement	57
Calculating Education Allowances	57
Calculating Gratuity Earnings	57
Using Generation Control in Gratuity Calculation	58
Using Formulas in Gratuity Calculation	58
Calculating the Thirteen Month Pay	58
Understanding 13th Month Pay Proration	58
Using Generation Control in the 13th Month Pay Calculation	59
Calculating Cash Advances	59
Calculating Absence and Termination Earnings	60
Calculating Annual Leave Instead of Annual Leave Entitlement	60
Calculating 80 Percent of Daily Wages	61
Calculating Leave Without Pay (LWOP)	61
Calculating Leave Without Pay (LWOP2)	62
Calculating Severance and Long Service Payments	62
Calculating 13th Month Payment on Termination	63
Calculating Amount Earnings	63
Flat Amounts	63
Formula-Based Amounts	64
Calculating Mandatory Provident Fund Earnings	64
Calculating Rolling Average Earnings	65
Understanding Rolling Average Earnings	66
Using Accumulators in the Rolling Average Calculation	66
Using Variables in the Rolling Average Calculation	67
Using Formulas in the Rolling Average Calculation	67
Working with Rolling Average (Example)	67
Controlling the Maximum Frequency Amount	68
Controlling Earnings Maximum or Goal Amount	69
Scheduling Earnings Using Generation Control	69

Chapter 7

Defining Deductions	71
Understanding Deductions for Hong Kong	71
Understanding Delivered Deduction Elements	71
Delivered Deduction Elements	72
Process Lists and Sections	73
Viewing Delivered Elements	73
Calculating Cash Advance Recovery	74
Calculating Community Chest	74
Calculating Mandatory Provident Fund Deductions	75

Calculating Leave Without Pay and Daily Rate Deduction	76
Scheduling Deductions Using Generation Control	76

Chapter 8

Administering Mandatory Provident Fund Contributions	77
Understanding the Administration of Mandatory Provident Fund Contributions	77
Common Elements Used in This Chapter	78
Viewing Delivered Elements	79
Understanding MPF Proration Rules	80
The MPF PO REVLNT INCM Proration Rule	80
The MPF PO 18TH BTHDAY Proration Rule	81
MPF PO 65TH BTHDAY Proration Rule	81
Making Statutory and Customary MPF Deductions	82
Accommodating MPF Exemption Rules and Limits	84
Understanding Accommodating MPF Exemption Rules and Limits	84
Understanding the MPF Contribution Holiday Rule	85
Understanding MPF Age Eligibility Rules	85
Understanding MPF Permitted Period Termination Rules	87
Defining Casual Employees for MPF Contributions	88
Excluding Employees from MPF Calculations	88
Applying Maximum and Minimum Limits to MPF Contributions	89
Calculating Permitted Period MPF Contributions	91
Understanding Permitted Period MPF Contributions	91
Calculating Employer Mandatory Permitted Period MPF Contributions	92
Calculating Employee Mandatory Permitted Period MPF Contributions	92
Calculating Employer and Employee Voluntary Permitted Period MPF Contributions	93
Calculating Regular MPF Contributions	93
Calculating Employers Regular Mandatory MPF Contributions	94
Calculating Employees Regular Mandatory MPF Contributions	95
Calculating Employer Regular Voluntary MPF Contributions	95
Calculating Employees Regular Voluntary MPF Contributions	96
Setting up Additional MPF Recipient Details	96
Submitting the Remittance Statement	97

Chapter 9

Running Banking and Recipient Processes	99
Understanding Banking and Recipient Processing	99
Understanding the Hong Kong Banking Process Flow	100
Common Elements Used in This Chapter	101
Viewing Delivered Elements	101

Linking Source Banks To Pay Entities	101
Page Used to Link Source Banks To Pay Entities	102
Linking Source Banks To Pay Entities	102
Setting Up Additional Mandatory Provident Fund Report Details	103
Pages Used to Set up Additional Mandatory Provident Fund Report Details	103
Setting up Recipient Commission and MPF Scheme Details	104
Linking Employees to Recipients by Membership Number	106
Managing Electronic Fund Transfers to Recipients	106
Understanding the EFT HSBC File	106
Pages Used to Manage Electronic Fund Transfers to Recipients	108
Creating the EFT HSBC File	108
Generating Recipient Payment Report Files	110
Understanding Recipient Payment Files	110
Pages Used to Generate Recipient Payment Files	111
Creating the Recipient Payment File	111
Processing Manual and Separate Cheques	112
Processing Manual Cheques Using Calendars	112
Processing Separate Cheques	113

Chapter 10

Printing and Viewing Payslips	115
Printing Payslips	115
Understanding Payslip Printing	115
Viewing Delivered Elements	115
Page Used to Print Payslips	116
Printing Payslips	116
Overriding Payslip Delivery Options	117
Page Used to Override Payslip Delivery Options	117
Viewing Payslips Online	117

Chapter 11

Managing Off-Cycle Payments for Hong Kong	119
Understanding Off-Cycle Processing	119
The Off-Cycle Process	119
Types of Off-Cycle Transactions	120
Viewing Delivered Elements	120
Recording Manual Payments for Hong Kong	120
Manual Payments	120
Entering Corrections for Hong Kong	121
Corrections	121

Making Unscheduled Payments for Hong Kong	122
Advancing Payrolls for Hong Kong	122

Chapter 12

Processing Inland Revenue Reports	123
Understanding Hong Kong Inland Revenue Reporting	123
Generating Inland Revenue Report Data	124
Understanding the Inland Revenue Report Data Creation Process	125
Viewing Delivered Elements	125
Page Used to Generate Inland Revenue Report Data	125
Generating IR56 Report Data	125
Reviewing and Maintaining IR56 Report Data	129
Understanding Inland Revenue Reporting Generated Data Inquiry Pages	129
Pages Used to Review and Maintain IR56 Report Data	130
Maintaining IR56 Personal Details	130
Maintaining IR56 Monetary Details	132
Generating the IR56B Electronic File	135
Understanding Flat File Generation	135
Page Used to Generate the IR56B Electronic File	135
Generating the IR56B Electronic File	135
Running Inland Revenue Reports	136
Pages used to Run Inland Revenue Reports	137

Chapter 13

Defining Absence Rules	139
Understanding Absence Rules for Hong Kong	139
Common Elements Used in This Chapter	140
Understanding Delivered Absence Primary Elements	140
Absence Entitlements Elements	140
Absence Take Elements	142
Viewing Delivered Elements	144
Calculating Annual Leave	144
Understanding Absence Forfeiture	144
Understanding Leave Accrual	144
Calculating Annual Leave for General Employees	145
Calculating Annual Leave for Statutory Employees	146
Calculating Absence Entitlements on Termination	147
Calculating Unused Annual Leave	147
Calculating 13th Month Payment	148
Calculating Severance and Long Service Leave Payments	149

Paying Outstanding Deduction Recovery Upon Termination	150
Calculating Sick Leave	151
Understanding Sick Leave	151
Calculating Sick Leave Payments	151
Calculating Maternity Leave	152
Understanding Maternity Leave	152
Calculating Maternity Leave	152
Calculating Leave Without Pay	153
Understanding Leave Without Pay	153
Calculating Leave Without Pay	154
Calculating Other Leave	154
Understanding Other Leave	155
Calculating Other Leave	155

Appendix A

Appendix: Global Payroll for Hong Kong Reports	157
Global Payroll for Hong Kong Reports: A to Z	157
Mandatory Provident Fund Reports	157
Recipient Payment Reports	158
Inland Revenue - Legislative Reports	158
Payslip Report	159

Index	161
--------------------	------------

PeopleSoft Enterprise Global Payroll for Hong Kong Preface

This preface discusses:

- PeopleSoft products.
- PeopleSoft Enterprise HRMS Application Fundamentals.
- Global Payroll documentation.

PeopleSoft Products

This PeopleBook refers to the following PeopleSoft product: PeopleSoft Enterprise Global Payroll for Hong Kong.

PeopleSoft Enterprise HRMS Application Fundamentals

Additional, essential information describing the setup and design of your system appears in a companion volume of documentation called *PeopleSoft Enterprise HRMS 9.1 Application Fundamentals PeopleBook*.

See Also

PeopleSoft Enterprise HRMS 9.1 Application Fundamentals PeopleBook, "PeopleSoft Enterprise HRMS Application Fundamentals Preface"

Global Payroll Documentation

This section discusses:

- Global Payroll application design.
- Global Payroll documentation structure.
- Documentation roadmap.

Global Payroll Application Design

Because the structure of the Global Payroll documentation is similar to the design of the application, the best way to understand the documentation is to review the design of the application itself.

Global Payroll is composed of two complementary parts:

- A core payroll application that includes:
 - A payroll rules engine.
 - A payroll processing framework.
 - Processes and setup steps that apply to all countries.
- Country extensions that include:
 - Statutory and customary objects (payroll rules, payroll processes, reports, additional country-specific pages, and self-service applications).
 - Country-specific rules and elements.

Global Payroll Documentation Structure

Like the application, the documentation for Global Payroll consists of two parts: a core book and separate country extension books.

Core Documentation

Like the core portion of the application, which applies to all countries and enables you to develop rules and process a payroll regardless of location, the core book is country neutral. Thus, while it describes the core set of tools that you can use to develop a payroll, it doesn't discuss the local country rules that have been set up for you. For information about how the PeopleSoft system has extended core capabilities to meet local requirements, refer to the country extension documentation.

Country Extension Documentation

Just as country extensions in the application address local needs, the country extensions in the documentation cover local functionality. This includes:

- Any core feature with local extensions.
- Country-specific rule setup.
- PeopleSoft-delivered rules and tables.
- Country-specific pages.
- Country-specific reports.
- PeopleSoft Enterprise Human Resources Management Systems (PeopleSoft HRMS) setup, such as bank definitions, that varies by country.
- Implementation information that varies by country.

Documentation Roadmap

The core and the country extension documentation complement each other, therefore, it is important to read both sets of documentation.

What to Read When

You can approach the documentation in the following way:

- If a process setup is shared between the core application and the country extension, read the core documentation first and then the country extension documentation.

For example, banking is a feature that you first define in the core application and then often continue in the country extension, because most country extensions have some type of banking functionality. You would first read the banking chapter in the core documentation and then the banking chapter in the country extension documentation.

- If a process is set up only in the core application, read the core documentation.
- If a process is set up only in the country extension, read the country extension documentation.

Documentation Audiences

We've identified the following audiences for the documentation:

- Technical

Technical readers who are interested in the technical design of the product should begin by reading the "Introducing the Core Application Architecture" section of the core documentation, as well as the batch processing information that is mentioned in many of the other sections.

See *PeopleSoft Enterprise Global Payroll 9.1 PeopleBook*, "Introducing the Core Application Architecture."

- Functional

Functional readers who are interested in defining rules should begin by reading the country-specific functionality described in the country extension documentation. Functional readers can continue to learn about how to use the tools in the core application by reading the sections on defining payroll elements, such as earnings and deductions, in the core documentation.

- Managerial

Managerial readers should begin by reading the introduction sections of both the core documentation and the country extension documentation to get a high-level overview of the Global Payroll product.

Note. To fully understand Global Payroll, technical or functional persons who are involved in the product implementation should read the core documentation and the applicable country extension documentation in their entirety.

PeopleBooks and the PeopleSoft Online Library

A companion PeopleBook called *PeopleBooks and the PeopleSoft Online Library* contains general information, including:

- Understanding the PeopleSoft online library and related documentation.
- How to send PeopleSoft documentation comments and suggestions to Oracle.
- How to access hosted PeopleBooks, downloadable HTML PeopleBooks, and downloadable PDF PeopleBooks as well as documentation updates.
- Understanding PeopleBook structure.
- Typographical conventions and visual cues used in PeopleBooks.
- ISO country codes and currency codes.
- PeopleBooks that are common across multiple applications.
- Common elements used in PeopleBooks.
- Navigating the PeopleBooks interface and searching the PeopleSoft online library.
- Displaying and printing screen shots and graphics in PeopleBooks.
- How to manage the locally installed PeopleSoft online library, including web site folders.
- Understanding documentation integration and how to integrate customized documentation into the library.
- Application abbreviations found in application fields.

You can find *PeopleBooks and the PeopleSoft Online Library* in the online PeopleBooks Library for your PeopleTools release.

Chapter 1

Getting Started with Global Payroll for Hong Kong

This section provides an overview of Global Payroll for Hong Kong and discusses:

- Global Payroll for Hong Kong business processes.
- Global Payroll for Hong Kong integrations.
- Global Payroll for Hong Kong implementation.

Global Payroll for Hong Kong Overview

Global Payroll for Hong Kong delivers elements, rules, pages, processes, and reports that work with the PeopleSoft Enterprise Global Payroll core application to form a complete payroll package for Hong Kong.

Global Payroll for Hong Kong delivers earnings for hourly and salaried employees, as well as overtime, shift allowances, typhoon and black rain allowances, meal allowances, meal reimbursement, housing allowances, gratuity, absence and termination earnings, and 13th month pay. Global Payroll for Hong Kong also delivers many common deductions, such as those for cash advance recovery, community chest, leave without pay, and Mandatory Provident Fund deductions. With Global Payroll for Hong Kong, you can capture, generate, and maintain both employee and company identification and biographical data that support the reporting requirements of the Hong Kong Inland Revenue Department. You can process absence payments and also absence payments on termination for employees. You can set up and run the banking process and process paychecks. With Global Payroll for Hong Kong, you can design and generate payslips.

Global Payroll for Hong Kong Business Processes

The following list is of the Global Payroll for Hong Kong business processes:

- Inland Revenue reporting.
- Mandatory Provident Fund.
- Printing and viewing payslips.
- Payroll reporting.
- Absence and termination.
- Banking and recipient processing.

We discuss these business processes in the business process chapters in this PeopleBook.

Global Payroll for Hong Kong Integrations

Global Payroll for Hong Kong integrates with these applications through the core Global Payroll application:

- PeopleSoft Enterprise Human Resources.
- PeopleSoft Enterprise Time and Labor.
- PeopleSoft Enterprise General Ledger.

We discuss integration considerations in the core Global Payroll PeopleBook.

See Also

PeopleSoft Enterprise Global Payroll 9.1 PeopleBook, "Working with Payee Data"

PeopleSoft Enterprise Global Payroll 9.1 PeopleBook, "Integrating with PeopleSoft Enterprise Time and Labor"

PeopleSoft Enterprise Global Payroll 9.1 PeopleBook, "Integrating with PeopleSoft Enterprise General Ledger"

Global Payroll for Hong Kong Implementation

PeopleSoft Setup Manager enables you to generate a list of setup tasks for your organization based on the features that you are implementing. The setup tasks include the components that you must set up, listed in the order in which you must enter data into the component tables, and links to the corresponding PeopleBook documentation.

Other Sources of Information

In the planning phase of your implementation, take advantage of all PeopleSoft sources of information, including the installation guides, table-loading sequences, data models, and business process maps.

See Also

Enterprise PeopleTools PeopleBook: PeopleSoft Setup Manager

Enterprise PeopleTools PeopleBook: PeopleSoft Component Interfaces

Chapter 2

Understanding Global Payroll for Hong Kong

This chapter provides an overview of Global Payroll for Hong Kong and discusses:

- Global Payroll for Hong Kong business processes.
- Delivered elements for Hong Kong.
- Delivered elements naming convention.
- Archiving data for Global Payroll for Hong Kong.

Understanding Global Payroll for Hong Kong

Global Payroll for Hong Kong is a country extension of the core Global Payroll application. It provides the payroll rules, elements, and absence processes needed to run a Hong Kong payroll.

Important! If you want to use the delivered rules for this country extension, we recommend that you use only employment instances in PeopleSoft Enterprise Human Resources.

Global Payroll for Hong Kong Business Processes

Global Payroll for Hong Kong supports the following business processes:

- Inland Revenue Reporting.

This feature satisfies the requirements of the Hong Kong Inland Revenue Department (IRD). Features include the ability to capture, generate, and maintain both employee and company identification and biographical data that support the reporting requirements of the Hong Kong Inland Revenue Department (IRD).

PeopleSoft provides you with the ability to create a flat file that complies with Hong Kong Inland Revenue Department requirements for the submission of electronic files. A Global Payroll core application process creates the output using a file layout object that has the same structure as that of the electronic file expected by the IRD of Hong Kong. Before you generate, review, and print Inland Revenue forms and reports, you can set up additional report data. Employee departure details, housing and quarters details, and employer details are required for specific Inland Revenue reports. You can also associate multiple payroll accumulators with report elements and allocate starting sheet numbers. After you set up and generate the data required for Inland Revenue reporting and generate those forms, you can review the results and maintain available fields. The IR56 Inquiry component enables you to view and amend the generated IR56 data.

- Mandatory Provident Fund.

This feature supports the administrative and reporting requirements of Mandatory Provident Fund (MPF) administration and maintenance and provides support for both employee and employer payments to a nominated fund in accordance with the calculation of eligibility rules for MPF legislation. These deduction rules cover legislative MPF requirements such as permitted period processing, age eligibility, and the contribution holiday rule. The system accommodates MPF exemption rules and limits by enabling you to define casual employees for MPF contributions, exclude specific employees from MPF calculations and apply maximum and minimum limits to MPF contributions.

MPF reports such as the Remittance Statement and Employee New/Terminated Report enable you to manage your contributions. You can also set up recipient MPF commission and scheme details for your MPF reports.

- Payslips.

The design of the payslip feature enables you to create and control payslips that display the data that you want, where you want it and in the format that you want. You can override templates at lower levels, so you do not have to create multiple templates to cover every payslip scenario that you may have.

- Payroll Reporting.

In addition to the reports delivered with Global Payroll, the Hong Kong country extension comes with a set of reports to support business requirements. Reports included in the country extension are:

- Payroll Register
- Reconciliation Report
- Pay Component Register

- Absence and Termination.

Global Payroll for Hong Kong delivers predefined rules for processing absence payments, such as annual leave, long service leave, sick leave, maternity leave, and jury leave. We also deliver rules to calculate absence entitlements on termination, including rules for the payment of unused annual leave, 13th month payment, outstanding deduction recovery, severance, and long service. You can modify many of these rules to reflect absence and termination policies that are specific to the organization or to labor agreements with employees.

To demonstrate how Global Payroll can process typical absence requirements in Hong Kong, PeopleSoft provides 8 absence entitlement elements and 10 absence take elements.

- Banking and Recipient Processing.

This feature supports net payment (employee salary) direct deposits and recipient payments using the electronic file (HSBC) format used by the Hong Kong and Shanghai Corporation Bank. Global Payroll for Hong Kong generates electronic file outputs to credit employee salaries and reports this data to the recipient. The Global Payroll banking process brings together payroll data, pay entity source bank data, and payee or recipient bank data. The EFT file creation process extracts data compiled by the banking process according to the content you want in the EFT file that you are creating, merges it with data provided by the Hong Kong country extension and creates the file for transmission.

See Also

PeopleSoft Enterprise Global Payroll 9.1 PeopleBook, "Generating Report Data," Understanding Report Data Generation

Chapter 10, "Printing and Viewing Payslips," page 115

Chapter 8, "Administering Mandatory Provident Fund Contributions," page 77

Chapter 9, "Running Banking and Recipient Processes," page 99

Chapter 13, "Defining Absence Rules," page 139

Chapter 4, "Setting Up Inland Revenue Reports," page 21

Delivered Elements for Hong Kong

This section discusses:

- Creation of delivered elements.
- Element ownership and maintenance.

Creation of Delivered Elements

Global Payroll defines each business process for Hong Kong in terms of delivered elements and rules. Some of these elements and rules are specifically designed to meet legislative requirements, while others support common or "customary" payroll practices.

All of the elements and rules delivered as part of the country extension were created using the core application—the same application you use to create additional elements or rules and configure existing elements delivered as part of the Global Payroll system. Because the tools needed to redefine or create new payroll elements are fully documented in the core application PeopleBook, we do not reproduce this information here. Instead, we briefly review the relationship between the core application (which contains the tools you need to define your own elements and rules) and the country extensions (which contain country-specific rules and elements defined by PeopleSoft).

The core application has the following characteristics:

- It consists of a payroll rules engine—a flexible tool that enables users to define the rules and elements of their payroll system and execute payroll and absence calculations. Global Payroll does not embed payroll-specific logic or computations in application code. Instead, it specifies all business application logic, such as earnings, deductions, absences, and accumulators, in terms of payroll rules and elements. Global Payroll enables the user to enter and maintain payroll rules through a set of pages and offers a comprehensive set of features that enable the user to work in their preferred language or currency.
- It provides a payroll processing framework—a flexible way to define and execute payroll and absence processing flows, such as calendars, run types, pay periods, and process lists.

Country extensions have the following characteristics:

- They are built using the core application.
- They consist of statutory and customary objects (country-specific payroll rules, elements, payroll processes, reports, pages, and self-service applications).

PeopleSoft delivers a query that you can run to view the names of all delivered elements designed for Hong Kong. Instructions for running the query are provided in the *PeopleSoft Enterprise Global Payroll 9.1 PeopleBook*.

See Also

PeopleSoft Enterprise Global Payroll 9.1 PeopleBook, "Viewing Delivered Elements," Understanding How to View Delivered Elements

Element Ownership and Maintenance

The delivered elements and rules of your Global Payroll country extension can be classified according to whether they are owned and maintained by the customer or by PeopleSoft. Some elements and rules are maintained exclusively by PeopleSoft and cannot be modified, while others can be configured to meet requirements unique to each organization.

Understanding Element Ownership in Global Payroll

There are five categories of element ownership:

PS	Elements delivered and maintained on an ongoing basis by PeopleSoft.
Delivered/Maintained	

PS Delivered/Not Maintained	Elements delivered by PeopleSoft that must be maintained by the customer. This category consists primarily of either customary (non-statutory) rules or statutory elements that customers may want to define according to a different interpretation of the rules. Although PeopleSoft may occasionally update elements defined as <i>PS Delivered/Not Maintained</i> , you are not required to apply these updates.
Customer Maintained	Elements created and maintained by your organization. PeopleSoft does not deliver rules defined as <i>Customer Maintained</i> .
PS Delivered/Customer Modified	Elements that were originally PS Delivered/Maintained elements over which the customer has decided to take control (this change is irreversible).
PS Delivered / Maintained / Secure	Delivered elements that the customer can never modify or control.

Understanding Element Ownership in Global Payroll for Hong Kong

Of the five ownership categories listed in the previous section, only PS Delivered/Maintained and PS Delivered/Not Maintained are used to define Hong Kong elements. Although Global Payroll for Hong Kong delivers some elements as PS Delivered/Maintained, the large majority of elements are designated PS Delivered/Not Maintained. This enables you to modify, update, and reconfigure the delivered elements to meet needs that are specific to your organization.

In the following table of elements supplied with Global Payroll for Hong Kong, the *ownership* of all elements is PS Delivered/Not Maintained with exceptions shown in column 2.

Note. These element types have no exceptions so are not shown in the table: absence entitlements, accumulators, arrays, absence takes, brackets, durations, dates, element groups, earnings, generation controls, proration rules, processes, sections, and writable arrays.

<i>Element Type</i>	<i>Exceptions</i>
Deductions	MPF employee and employer (regular and permitted—mandatory deductions).
Formulas	MPF formulas related to: <ul style="list-style-type: none"> • Base for employee and employer mandatory calculations. • Post processing for employee and employer mandatory calculations. • Pre processing for employee and employer mandatory calculations. • Resolution of employee and employer mandatory calculations.
Manage Historical Data Rules	Historical rule for employee MPF mandatory calculations.
Variables	MPF — Total voluntary contribution for permitted period.

See Also

PeopleSoft Enterprise Global Payroll 9.1 PeopleBook, "Getting Started with Global Payroll"

Delivered Elements Naming Convention

This section discusses:

- Element names.
- Functional area codes.
- Element type codes (PIN_TYPE).
- Viewing delivered elements.

Element Names

One of the keys to understanding how delivered payroll elements function in the system is to understand their names. Understanding the naming convention developed for PeopleSoft-delivered elements can help you determine how an element is used, the element type, and even the functional area it serves. Depending on whether the element is a primary element, a component of a primary element, or a supporting element, one of the following naming conventions applies.

Supporting Elements

For supporting elements, such as variables, formulas, dates, durations, and so on, PeopleSoft uses the following naming convention: FFF (or FF) TT NAME.

- FFF (or FF): Functional Area Code (see Functional Area Codes for more information).
- TT: Type of Supporting Element (see List Element Type Codes (PIN_TYPE) for more information).
- NAME (or NAME NAME): An indication of what the element does or is for. (The number of NAME components may vary.)

For example, in the MPF variable MPF VR START DATE, MPF stands for Mandatory Provident Fund, VR stands for variable and START DATE stands for start date. The element's thirty character (maximum) description (DESCR) provides a fuller explanation of what the element does or is for.

Primary Elements

Primary elements, such as earnings, deductions, absence take, and absence entitlement elements often do not contain functional area codes or element type codes in their names. This is because primary elements have names, based on Hong Kong terms, that identify their function and element type without the use of additional codes. For example, the name of the earning element 13MTHPAY clearly identifies this element as an earning, and more specifically, as a thirteenth month (13MTH) payment (PAY).

Additional Clues to the Use of Hong Kong Elements

Many Hong Kong elements contain abbreviations that provide clues (beyond those provided by the functional area codes or element type codes) to their use in the system. For example, consider the following duration element: TER DR DY IN SERV. The functional area code TER indicates that this element is used for termination elements, and the element type code DR identifies it as a duration element. The abbreviations DY, IN and SERV provide additional clues about how the element measures periods of time. The duration is in days (DY) in (IN) service (SERV). As you become more familiar with the payroll rules created for Hong Kong, these abbreviations will help you to further identify and understand the role played by each element.

The following table lists the most common abbreviations used in the names of Hong Kong elements.

<i>Abbreviation</i>	<i>English</i>
AC	Accumulator
ADV	Advance
ALLOW	Allowance
AMT	Amount
ANNIV	Anniversary
BAL	Balance
BAS	Basic
CAL	Calendar
CNTR	Contract
COMCHST	Community Chest
COMP	Compassion
CUR	Current
DED	Deductions
DY	Days
ED	Education
EE / EMP	Employee
ELIG	Eligibility
ENT	Entitlement
ER	Employer
ERN	Earnings
EXT	Extract
FCAST	Forecast

Abbreviation	English
GENL	General
HOL	Holiday
HLY	Hourly
INCM	Income
LSP	Long service payment
LWOP	Leave without pay
MARR	Marriage
MAT	Maternity
MAX	Maximum
MIN	Minimum
MN	Mandatory
MSG	Message
MTD	Month to date
MTH	Month
PERM	Permitted
PRD	Period
PREV	Previous
PRIM	Primary
REG	Regular
REVLNT	Relevant
ROLLAVG	Rolling average
RSLV	Resolve
SAL	Salary
STAT	Statutory
SVC / SERV	Service
TOT	Total
TX	Tax
VOL	Voluntary
YR	Year

Abbreviation	English
YTD	Year to date

Component Names (Suffixes)

In Global Payroll for Hong Kong, suffixes are used to name the components of earning and deduction elements. For example, when you create an earning or deduction element in Global Payroll, you define the components that make up the element, such as base, rate, unit, and percentage. The system automatically generates the components and accumulators for the element based on the calculation rule or accumulator periods. The system also names the components and accumulators by appending a suffix to the element's name.

For example, let's say you define the earning element named EARN1 with the following calculation rule:

$EARN1 = Rate \times Unit$

The system automatically creates two additional elements for the components in the calculation rule: a rate element called EARN1_RATE and a unit element called EARN1_UNIT. In Global Payroll for Hong Kong, all suffixes fall into one of the following types:

- Separator.
- Earnings and deductions and absence entitlement component suffixes.
- Earnings and deductions and absence entitlement accumulator suffixes.
- Deduction arrears component suffixes.
- Deduction arrears accumulator suffixes.
- Recipient suffixes.

Note. To view the suffixes used for Hong Kong, navigate to Set Up HRMS, Product Related, Global Payroll & Absence Mgmt, System Settings, Element Suffixes.

Functional Area Codes

The following table contains the functional area codes used in the names of Hong Kong elements:

Functional Area Code	Description
ABS	Absence
ALV	Annual leave
CM	Areas common to multiple functional areas
DED	Deductions
ERN	Earnings
IRR	Inland Revenue Reporting

Functional Area Code	Description
MLV	Maternity Leave
MPF	Mandatory Provident Fund
NPL	No pay leave
OLV	Other leave
PSLP	Payslips
SLV	Sick leave
TER	Terminations

See Also

PeopleSoft Enterprise Global Payroll 9.1 PeopleBook, "Defining General Element Information"

Element Type Codes (PIN_TYPE)

Many element types, particularly supporting elements, are identified by the type code in their name. For example, the FM in MPF FM POST EEMN1 identifies the element as a formula.

You can see all the element types in the search page when you navigate to Set Up HRMS, Product Related, Global Payroll & Absence Mgmt, System Settings, Element Types. Because not all element types are delivered for Hong Kong, not all of these codes appear in the names of Hong Kong elements.

See Also

PeopleSoft Enterprise Global Payroll 9.1 PeopleBook, "Defining General Element Information"

Viewing Delivered Elements

PeopleSoft delivers a query that you can run to view the names of all delivered elements designed for Hong Kong. Instructions for running the query are provided in the *PeopleSoft Enterprise Global Payroll 9.1 PeopleBook*.

See Also

PeopleSoft Enterprise Global Payroll 9.1 PeopleBook, "Viewing Delivered Elements," Understanding How to View Delivered Elements

Archiving Data for Global Payroll for Hong Kong

PeopleSoft Enterprise Global Payroll for Hong Kong generates a large amount of result data. To keep the amount of saved data manageable, it can be helpful to archive it periodically. PeopleSoft PeopleTools delivers an archiving tool called the Data Archive Manager. To aid you in archiving your result data using the Data Archive Manager, PeopleSoft Global Payroll for Hong Kong delivers a predefined archive object (GPHK_RSLT_ARCHIVE) and archive template (GPHKRSLT). The delivered archive template uses queries that select data by calendar group ID (CAL_RUN_ID field).

Note. Please use extreme caution when making changes to delivered archive objects, queries, or templates. Any modifications can result in the loss of important data.

See *PeopleSoft Enterprise Global Payroll 9.1 PeopleBook*, "Archiving Data."

Chapter 3

Setting Up Global Payroll for Hong Kong

This chapter discusses how to:

- Process retroactive payments.
- Enter additional information for other features.
- Define trigger and segmentation events for Hong Kong.
- Identify proration rules.

Processing Retroactive Payments

This section discusses the default retro method of forwarding and the ability to change it to the corrective method.

The default retro method and the on conflict retro method for Hong Kong are both forwarding. Global Payroll core application retro processing meets all requirements for processing retroactive payments in Hong Kong.

While forwarding retro is the default retro method for Hong Kong, you can still use the corrective retro method. If you use corrective retro, ensure that all periods before the start of the current tax year (April 1 to March 31) are forwarded to the current year. For example, if in May an employee was paid a backdated increase for the period January to April, you can use corrective retro for the period in the current tax year (April), but use forwarding retro for the period in the prior tax year (January to March).

Note. Some elements that have monthly limits, such as Mandatory Provident Fund elements, have accumulators with corrective retro behavior. This ensures that calculations are always based on an updated accumulator. If you define accumulators with corrective behavior but then forward some deltas to the current period that is contributing to this accumulator, verify that you end up with the correct numbers.

See Also

PeopleSoft Enterprise Global Payroll 9.1 PeopleBook, "Defining Retroactive Processing"

Entering Additional Information for Other Features

The following additional pages are used specifically for set up required for Global Payroll Hong Kong. They are documented in full in their respective sections as shown in the following list:

- IR56 Report Data HKG; Setting Up Inland Revenue Reports.
- Tax Reference Number Dtls HKG; Setting Up Inland Revenue Reports.
- IR56 Exchange Rate Defn HKG; Setting Up Inland Revenue Reports.
- Define IR56B/M Controls HKG; Setting Up Inland Revenue Reports.
- Overseas Concern Details HKG; Setting Up Inland Revenue Reports.
- Source Bank Accounts HKG; Running Banking and Recipient Processing.
- Deduction Recipients HKG; Running Banking and Recipient Processing.
- Link to Pay Group HKG; Setting Up Payslips.
- Templates HKG; Setting Up Payslips.
- Messages HKG ; Setting Up Payslips.

See Also

Chapter 4, "Setting Up Inland Revenue Reports," page 21

Chapter 9, "Running Banking and Recipient Processes," page 99

Chapter 5, "Setting Up Payslips," page 35

Defining Triggers and Segmentation Events for Hong Kong

This section discusses:

- Triggers.
- Segmentation events.
- Viewing delivered elements.

Triggers

The following is a list of triggers for Hong Kong:

<i>Record (Table) Name</i>	<i>Type</i>	<i>Trigger Event ID</i>
ADDRESSES	Iterative	NA
COMPENSATION	Iterative	NA

Record (Table) Name	Type	Trigger Event ID
COMPENSATION	Retro	COMPENSATI
CONTRACT_DATA	Iterative	NA
EMPLOYMENT	Iterative	NA
GPAU_EE_TAX_DTL	Iterative	NA
GPAU_GARN_DTLS	Iterative	NA
GPAU_LSL_HISTRY	Iterative	NA
GP_ABSEVT_SGPAU	Iterative	NA
GP_ABS_EVENT	Iterative	NA
GP_ABS_EVENT	Retro	GPABSEVENT
GP_ABS_OVRD	Iterative	NA
GP_ABS_OVRD	Retro	GPABSOVRD
GP_PI_MNL_DATA	Iterative	NA
GP_PI_MNL_DATA	Retro	GPPIMNLDAT
GP_PI_MNL_SOVR	Iterative	NA
GP_PI_MNL_SOVR	Retro	GPPIMNLISOV
GP_PYE_OVRD	Iterative	NA
GP_PYE_OVRD	Retro	GPPYEOVRD
GP_PYE_OVR_SOVR	Iterative	NA

Record (Table) Name	Type	Trigger Event ID
GP_PYE_OVR_SOVR	Retro	GPPYEOVRSO
GP_PYE_SECT_DTL	Iterative	NA
GP_PYE_SECT_DTL	Retro	GPPYESECTD
GP_RTO_TRGR	Iterative	NA
GP_RTO_TRG_CTRY	Iterative	NA
GP_SEG_TRGR	Iterative	NA
JOB	Iterative	NA
JOB	Retro	JOB
JOB	Segmentation	NA
JOB_JR	Iterative	NA
PERSON	Iterative	NA
PERS_DATA_EFFDT	Iterative	NA
SCH_ASSIGN	Iterative	NA
SCH_ASSIGN	Retro	SCHASSIGN
SCH_MNG_SCH_TBL	Iterative	NA
TL_PAYABLE_TIME	Iterative	NA
WKF_CNT_TYPE	Iterative	NA

See Also

PeopleSoft Enterprise Global Payroll 9.1 PeopleBook, "Setting Up Triggers"

Segmentation Events

The following is a list of segmentation events for Hong Kong:

Name	Description	Segment Type
COMPRATE	Comp rate segmentation	Element
GRADE	Grade segmentation	Element
JOB	Job segmentation	Period

See Also

PeopleSoft Enterprise Global Payroll 9.1 PeopleBook, "Defining Segmentation"

Viewing Delivered Elements

PeopleSoft delivers a query that you can run to view the names of all delivered elements designed for Hong Kong. Instructions for running the query are provided in the *PeopleSoft Enterprise Global Payroll 9.1 PeopleBook*.

See Also

PeopleSoft Enterprise Global Payroll 9.1 PeopleBook, "Viewing Delivered Elements," Understanding How to View Delivered Elements

Identifying Proration Rules

Five proration rules are available to the 15 supplied for all countries to meet Hong Kong's payroll processing requirements. The following table lists the rules and indicates the numerator and denominator the rule uses:

Name	Description	Numerator	Denominator
OE PO 13MTH	Proration for 13th mth pay	Formula OE FM 13MTH PAY	Duration OE DR DAYS IN YR

Name	Description	Numerator	Denominator
MPF PO 18TH BTHDAY	18th birthday proration	Duration MPF DR BIRTHDAY	Duration GP CAL DAYS PERIOD
MPF PO REVLNT INCM	Proration for relevant income	Duration MPF DR START DATE	Duration GP CAL DAYS PERIOD
MPF PO 65TH BTHDAY	65th birthday proration	Duration MPF DR 65 BTHDAY	Duration GP CAL DAYS SEG

See Also

PeopleSoft Enterprise Global Payroll 9.1 PeopleBook, "Defining Calculation Elements," Defining Proration Rules

Chapter 4

Setting Up Inland Revenue Reports

This section provides an overview of the setup for Hong Kong Inland Revenue (IR56) reporting and discusses how to:

- Link accumulators to report elements.
- Set up employee departure details.
- Set up principal employers for part-time employees.
- Set up employee housing quarter details.
- Set up self-employment data.
- Set up overseas concern details.
- Set up IR56B and IR56M starting sheet numbers.
- Set up tax reference number details.
- Set up exchange rate details.

Understanding Setup for Hong Kong Inland Revenue Reporting

Before you can generate, review, and print your Inland Revenue forms and reports, you must set up additional report data. Employee departure details, housing and quarters details, tax reference numbers and employer details are required for specific Inland Revenue reports. You can also associate multiple payroll accumulators with report elements, set up exchange rates and allocate starting sheet numbers.

Viewing Delivered Elements

The PeopleSoft system delivers a query that you can run to view the names of all delivered elements designed for Hong Kong. Instructions for running the query are provided in the *PeopleSoft Enterprise Global Payroll 9.1 PeopleBook*.

See Also

PeopleSoft Enterprise Global Payroll 9.1 PeopleBook, "Viewing Delivered Elements," Understanding How to View Delivered Elements

Linking Accumulators with Report Elements

To link accumulators to report elements, use the IR56 Report Data HKG (GPHK_IR56REP_SETUP) component.

This section provides an overview of accumulator usage in the IR56 result table and discusses how to link accumulators with report elements.

Understanding Accumulator Usage in the IR56 Result Table

You can select the payroll accumulators to link to specific IR56 report elements. During the data creation process, the year to date (YTD) balance amount is retrieved from the result table for the specific accumulators that you associate with each report element. The IR56 result table contains the total amount for each accumulator associated with each report element. You can view and modify the amounts. Amounts for the report element are grouped at the time of reporting (on the electronic file and hard copy output).

Page Used to Link Accumulators with Report Elements

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
IR56 Report Data HKG	GPHK_IR56REPT_TBL	Set Up HRMS, Product Related, Global Payroll & Absence Mgmt, Reports, IR56 Report Data HKG, IR56 Report Data HKG	Associate payroll accumulators with report elements. You can link accumulators to the report element.

Linking Accumulators with Report Elements

Access the IR56 Report Data HKG page (Set Up HRMS, Product Related, Global Payroll & Absence Mgmt, Reports, IR56 Report Data HKG, IR56 Report Data HKG).

IR56 Report Data HKG

IR56 Report Element: 01 Salary / Wages

Report Element Details Find | View All First 1 of 1 Last

Effective Date:

Accumulators associated with Report Element Customize | Find | View All | First 1-4 of 10 Last

	Element Name		*Operand		
1	BASSAL_FYTDA		Add		
2	BASHLY_FYTDA		Add		
3	OT1.5_FYTDA		Add		
4	SHNT1.3_FYTDA		Add		

IR56 Report Data HKG page

IR56 Report Element Displays predetermined categories that appear in Inland Revenue reports. You can associate multiple accumulators that must be reported against an IR56 report element.

Accumulators Associated with Report Element

Element Name Select the payroll accumulators to link to the IR56 report element.

During the data creation process, the year to date (YTD) balance amount is retrieved from the result table for the specific accumulators that you associate with each report element. The IR56 result table contains the total amount for each accumulator associated with each report element. You can view and modify the amounts. Amounts for the report element are grouped at the time of reporting (on the electronic file and hard copy output).

For example, when you associate three accumulators with the *Commission/Fees* report element, the IR56 result table contains three rows of data (one for each accumulator). At the time of reporting and printing, the amounts from the three accumulators are totaled and printed against the *Commission/Fees* report element.

Operand

Identify whether you want the accumulator to *Add* or *Subtract* when resolving.

Accumulators always store amounts as positive values. However, to attach an accumulator to a report element that is a negative amount, select *Subtract*. This informs the IR56 creation process that the amount associated with the accumulator should be treated as a negative amount.

For example, the accumulator LWOP_FYTDA for the leave without pay earning is attached to the *Salary/Wages* report element. The Payroll Result table has an amount of 1200. When you select *Subtract*, the 1200 is reduced from the total amount calculated for the *Salary/Wages* report element.

See Also

PeopleSoft Enterprise Global Payroll 9.1 PeopleBook, "Setting Up Accumulators"

[Chapter 12, "Processing Inland Revenue Reports," Generating Inland Revenue Report Data, page 124](#)

[Chapter 12, "Processing Inland Revenue Reports," Reviewing and Maintaining IR56 Report Data, page 129](#)

[Chapter 12, "Processing Inland Revenue Reports," Page Used to Generate the IR56B Electronic File, page 135](#)

Setting Up Employee Departure Details

This section discusses how to set up employee departure details.

Page Used to Set Up Employee Departure Details

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Specify Departure Details HKG	GPHK_DPRT_DTLS_HKG	Global Payroll & Absence Mgmt, Payee Data, Terminations, Specify Departure Details HKG, Specify Departure Details HKG	Capture the departure details of employees leaving Hong Kong. This information appears in the IR56G report. This information applies only to employees who are not citizens of the country. It is required when an overseas employee is terminated.

Setting Up Employee Departure Details

Access the Specify Departure Details HKG page (Global Payroll & Absence Mgmt, Payee Data, Terminations, Specify Departure Details HKG, Specify Departure Details HKG).

Specify Departure Details HKG

William Lee

Person ID: KH0001

Date of Departure:

01/01/2000

31

*Reason for Departure:

Expatriate - Move

Destination:

ABW

Aruba

Other Reason for Departure:

Expected Return Date:

31

Specify Departure Details HKG page

- Date of Departure

Displays the date on which an employee is expected to depart the country. This applies mainly to employees who come into the country for work and leave after a specified duration.
- Reason for Departure

Identify why the employee is leaving Hong Kong:
Expatriate - Move
Expatriate - Returning Home
Move to Another Country
Other
This information is required only for the IR56G report.
- Destination

Select the country to which the employee is departing.
- Other Reason for Departure

Enter a description if the reason for departure is *Other* (reasons for departure other than those specified by IRD).
- Expected Return Date

Enter the employee's expected date of return to Hong Kong.

See Also

- [Appendix A, "Appendix: Global Payroll for Hong Kong Reports," page 157](#)
- [Chapter 12, "Processing Inland Revenue Reports," Generating Inland Revenue Report Data, page 124](#)
- [Chapter 12, "Processing Inland Revenue Reports," Reviewing and Maintaining IR56 Report Data, page 129](#)
- [Chapter 12, "Processing Inland Revenue Reports," Generating the IR56B Electronic File, page 135](#)

Setting Up Principal Employers for Part-Time Employees

This section discusses how to set up principal employers for part-time employees.

You can enter the name of the employee's principal employer, which is an organization or agency to which a part-time employee actually belongs. The employee might be working for an organization but actually employed by another (principal) organization. If the information is available, it must be reported in the specific statutory report. This information is required only at the time of printing—it doesn't affect the data creation process.

Page Used to Set Up Principal Employers for Part-Time Employees

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Define PT EE Main Employer HKG (define part-time employee main employer HKG)	GPHK_PT_ER_HKG	Global Payroll & Absence Mgmt, Payee Data, Define PT EE Main Employer HKG, Define PT EE Main Employer HKG	Capture the name of the principal employer for part-time employees. Identifies employees who are working for one organization but are actually employed by another.

See Also

[Appendix A, "Appendix: Global Payroll for Hong Kong Reports," page 157](#)

[Chapter 12, "Processing Inland Revenue Reports," Generating Inland Revenue Report Data, page 124](#)

[Chapter 12, "Processing Inland Revenue Reports," Reviewing and Maintaining IR56 Report Data, page 129](#)

[Chapter 12, "Processing Inland Revenue Reports," Generating the IR56B Electronic File, page 135](#)

Setting Up Employee Housing Quarters Details

This section discusses how to set up employee housing quarter details.

Quarters are housing provided to employees by their employer. This benefit can be provided to local employees and expatriates. If employees are provided with housing quarters, the details must be reported on IR56 reports. This information is required only at the time of printing—it doesn't affect the data creation process.

Pages Used to Set Up Employee Housing Quarters Details

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Specify Housing Quarters HKG	GPHK_EMPL_QTRS	Global Payroll & Absence Mgmt, Payee Data, Specify Housing Quarters HKG, Specify Housing Quarters HKG	Capture housing quarter information.
Specify Housing Quarters HKG - Edit Address	EO_ADDR_HKG_SEC	Click the Edit Address link on the Specify Housing Quarters HKG page.	Enter or update the address details for the housing quarter. You can enter the area code, district, and address 1 – 3.

Setting Up Employee Housing Quarters Details

Access the Specify Housing Quarters HKG page (Global Payroll & Absence Mgmt, Payee Data, Specify Housing Quarters HKG, Specify Housing Quarters HKG).

Specify Housing Quarters HKG

William Lee Person ID: KH0001

Employee Residence Quarters Details Find | View All First 1 of 1 Last

***Quarters Number:**

Country: Hong Kong

Address: RM 4 7/F
BLK, SUI LAM ESTATE
SIMLAN
New Territories, SHATIN

[Copy Home Address](#)

[Edit Address](#)

Monthly Rent: ☐ Refund of Rent

Occupancy Begin Date: **Occupancy End Date:**

Nature of Quarters:

Amount Paid By

Employer to Landlord: <input type="text"/>	Employer to Employee: <input type="text"/>
Employee to Landlord: <input type="text"/>	Employee to Employer: <input type="text"/>

Yearly Amount Paid By

Employer to Landlord: <input type="text"/>	Employer to Employee: <input type="text"/>
Employee to Landlord: <input type="text"/>	Employee to Employer: <input type="text"/>

Specify Housing Quarters HKG page

Employee Residence Quarters Details**Quarters Number**

Displays a running serial number that enables you to enter multiple quarter information for a single employee.

A maximum of two housing quarters (for each employee) are reported on the IR56 reports. Which two rows are reported depends on the occupancy end date.

If an employee was provided with housing quarters at more than two locations in a tax year, a separate IR56B identifying the housing details must be reported. This additional report must contain the additional housing information (above the two locations).

You can enter information for more than two quarters per employee.

Country, Address, Copy Home Address, and Edit Address	Click the Copy Home Address button to populate the Address field from personal data. This is the address where the quarters are located. To change the default address details, click the Edit Address link to access the Edit Address page.
Monthly Rent	Enter the monthly rent amount here.
Refund of Rent	Select this check box if the employee has received a rent refund.
Occupancy Begin Date and Occupancy End Date	<p>Enter the dates on which the employee started and stopped occupying the quarters.</p> <p>When processing the data, the system selects the last two rows of housing quarter information. The information is reported if the period of occupation is during the tax year being processed.</p> <p>Housing quarters information is reported only if the occupancy dates overlap the processing period.</p> <p>Housing quarters information that does not have an occupancy end date is selected. Additionally, the occupancy end date that is closest to the period end date is also selected. (For IR56B and IR56M the period end date is the end of the tax year, while for IR56F and IR56G, the period end date is a value that you enter in the run control record.)</p>
Nature of Quarters	Enter text describing the quarters.
<i>Amount Paid By</i>	
Employer to Landlord, Employer to Employee, Employee to Landlord, and Employee to Employer	Enter the monthly amount paid by specific people for an employee occupying the housing quarters. This could be a rent refunded to the employee or employer or paid to the employee's landlord. These amounts are reported on the IR56 reports. This amount displays on the IR56 reports.
<i>Yearly Amount Paid By</i>	
Employer to Landlord, Employer to Employee, Employee to Landlord, and Employee to Employer	Enter the yearly amount paid by specific people for an employee occupying the housing quarters. This could be a rent refunded to the employee or employer or paid to the employee's landlord.

See Also

[Appendix A, "Appendix: Global Payroll for Hong Kong Reports," page 157](#)

[Chapter 12, "Processing Inland Revenue Reports," Generating Inland Revenue Report Data, page 124](#)

[Chapter 12, "Processing Inland Revenue Reports," Reviewing and Maintaining IR56 Report Data, page 129](#)

[Chapter 12, "Processing Inland Revenue Reports," Generating the IR56B Electronic File, page 135](#)

Setting Up Self-Employment Data

Under the provisions of the Hong Kong Business Registration Ordinance, a new business undertaken by an individual or a partnership must be registered with the Business Registration Office within one month of its commencement. If the employee is self-employed, you can enter their employer (trading) name and the business registration number.

Page Used to Set Up Self-Employment Data

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Define Self Employed Data HKG	GPHK_IR56_ER_HKG	Global Payroll & Absence Mgmt, Payee Data, Define Self Employed Data HKG, Define Self Employed Data HKG	Capture self-employment (employer) details including their employer (trading) name and the business registration number. This information is crucial for the IR56M report.

See Also

[Appendix A, "Appendix: Global Payroll for Hong Kong Reports," page 157](#)

[Chapter 12, "Processing Inland Revenue Reports," Generating Inland Revenue Report Data, page 124](#)

[Chapter 12, "Processing Inland Revenue Reports," Reviewing and Maintaining IR56 Report Data, page 129](#)

[Chapter 12, "Processing Inland Revenue Reports," Generating the IR56B Electronic File, page 135](#)

Setting Up Overseas Concern Details

To set up overseas concern details, use the Overseas Concern Details HKG (GPHK_OVSEAS_CNCRN) component.

You can create an identifier and enter the name of the overseas concern (outside Hong Kong). If the employee received an amount from an overseas concern, you must report the name and address of the organization that made the payment. You can enter the amount paid by the overseas concern on the IR56 Monetary Details page.

Page Used to Set Up Overseas Concern Details

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Overseas Concern Details HKG	GPHK_OVSEAS_CNCRN	Set Up HRMS, Product Related, Global Payroll & Absence Mgmt, Reports, Overseas Concern Details HKG, Overseas Concern Details HKG	Capture overseas concern details including their name and address.

See Also

[Appendix A, "Appendix: Global Payroll for Hong Kong Reports," page 157](#)

[Chapter 12, "Processing Inland Revenue Reports," Generating Inland Revenue Report Data, page 124](#)

[Chapter 12, "Processing Inland Revenue Reports," Reviewing and Maintaining IR56 Report Data, page 129](#)

[Chapter 12, "Processing Inland Revenue Reports," Generating the IR56B Electronic File, page 135](#)

[Chapter 12, "Processing Inland Revenue Reports," Maintaining IR56 Monetary Details, page 132](#)

Setting Up IR56B and IR56M Starting Sheet Numbers

You can enter the starting sheet number that is allocated to each of the employees for each pay entity in the tax year that you are reporting. The IR56B and IR56M reports include a sheet number (or serial number) that identifies the report for each employee when it is sent to the Inland Revenue Department. Legislation requires that sheet numbers for IR56B should start with 000001 and with 900001 for IR56M.

The data in the underlying table is created during the IR56B/M creation process. When you run the process, it determines whether a serial number exists for the selected pay entity and tax year. If a number is not found, the system creates a row with the default value of 0 for IR56B and 900000 for IR56M.

You can then reset the values if you have been testing the creation process and want to regenerate the data for the final time using the correct starting sheet number.

Note. If the pay entity is paying its employees in a foreign currency (and you are generating a manual IR56B), set the starting number for IR56B to 900000.

Page Used to Set Up IR56B and IR56M Starting Sheet Numbers

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Define IR56B/M Controls HKG	GPHK_IR56_CONTROL	Global Payroll & Absence Mgmt, Year-End Processing, Define IR56B/M Controls HKG, Define IR56B/M Controls HKG	Set up starting sheet numbers that identify the IR56 document for each employee when it is sent to the IRD. You can set the starting number for the IR56B and IR56M reports.

See Also

[Appendix A, "Appendix: Global Payroll for Hong Kong Reports," page 157](#)

[Chapter 12, "Processing Inland Revenue Reports," Generating Inland Revenue Report Data, page 124](#)

[Chapter 12, "Processing Inland Revenue Reports," Reviewing and Maintaining IR56 Report Data, page 129](#)

[Chapter 12, "Processing Inland Revenue Reports," Generating the IR56B Electronic File, page 135](#)

[Chapter 4, "Setting Up Inland Revenue Reports," page 21](#)

Setting Up Tax Reference Number Details

To set up tax reference number details, use the Tax Reference Number Dtls HKG (GPHK_TAXREF_TBL) component.

IR56 reports run by tax reference number, which has a major impact on the way the system creates and stores IR56 data. For every employee attached to the pay entity (sharing the tax reference number), the system combines amounts for each year to date element by currency code and stores them in the IR56 result tables. After the process is completed, you can use the IR56 Monetary Details page to enter adjustments to reflect the amount that should be reported on the IR56 documents.

The system captures the contact name, employer number and designation by tax reference number and retrieves the information from the GPHK_TAXREF_TBL.

Page Used to Set Up Tax Reference Number Details

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Tax Reference Number Dtls HKG	GPHK_TAXREF_TBL	Set Up HRMS, Product Related, Global Payroll & Absence Mgmt, Reports, Tax Reference Number Dtls HKG, Tax Reference Number Dtls HKG	Maintain tax reference number details required for IR56 reporting. You can enter a new tax reference number, create a description, select a signatory, and link multiple pay entities to the tax reference number. A primary indicator check box also enables you to select the main pay entity for the tax reference number.

See Also

[Appendix A, "Appendix: Global Payroll for Hong Kong Reports," page 157](#)

[Chapter 12, "Processing Inland Revenue Reports," Generating Inland Revenue Report Data, page 124](#)

[Chapter 12, "Processing Inland Revenue Reports," Reviewing and Maintaining IR56 Report Data, page 129](#)

[Chapter 12, "Processing Inland Revenue Reports," Generating the IR56B Electronic File, page 135](#)

[Chapter 4, "Setting Up Inland Revenue Reports," page 21](#)

Setting Up Exchange Rate Details

To set up exchange rate details, use the IR56 Exchange Rate Defn HKG (GPHK_IR56_EXCH_TBL) component.

Every year the Inland Revenue Department releases a date that you should use as a reference point for all currency conversion for IR56 reporting. If your organization pays its employees in a currency other than the local currency (HKD), you can maintain the conversion rate and the date used by the IR56 process. The IR56 Exchange Rate Definition page enables you to maintain currency details for a given tax year. The system uses these details for currency conversion when generating IR56 details.

Page Used to Set Up Exchange Rate Details

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
IR56 Exchange Rate Defn HKG	GPHK_IR56_EXCH_TBL	Set Up HRMS, Product Related, Global Payroll & Absence Mgmt, Reports, IR56 Exchange Rate Defn HKG, IR56 Exchange Rate Defn HKG	Maintain currency details for a given tax year. The details are used for currency conversion when generating IR56 details. For a specific tax year you can enter a rate type and the date from which the rate will apply.

See Also

[Appendix A, "Appendix: Global Payroll for Hong Kong Reports," page 157](#)

[Chapter 12, "Processing Inland Revenue Reports," Generating Inland Revenue Report Data, page 124](#)

[Chapter 12, "Processing Inland Revenue Reports," Reviewing and Maintaining IR56 Report Data, page 129](#)

[Chapter 12, "Processing Inland Revenue Reports," Generating the IR56B Electronic File, page 135](#)

[Chapter 4, "Setting Up Inland Revenue Reports," page 21](#)

Chapter 5

Setting Up Payslips

This document provides an overview of payslips, lists common elements, and discusses how to:

- Create payslip templates.
- Attach payslip templates to pay groups.
- Create payslip messages.

Understanding Payslips

The design of the payslip feature enables you to create and control payslips so that they display the data that you want and in the format that you want. You can override templates at lower levels, so you do not have to create multiple templates to cover every payslip scenario that you may have.

See Also

[Chapter 10, "Printing and Viewing Payslips," page 115](#)

Viewing Delivered Elements

The PeopleSoft system delivers a query that you can run to view the names of all delivered elements designed for Hong Kong. Instructions for running the query are provided in the *PeopleSoft Enterprise Global Payroll 9.1 PeopleBook*.

See Also

PeopleSoft Enterprise Global Payroll 9.1 PeopleBook, "Viewing Delivered Elements," Understanding How to View Delivered Elements

Description of Processes in Payslip Job

The Payslip page launches a Job (GPKKPYSL) containing two processes in sequence:

1. The Structured Query Report (SQR) GPHKPY01 prints the payslip report and provides self service related information for ePay if ePay is licensed.

2. The GP_EPAY Application Engine process uses the payslip report and self service related information provided by the prior processes in this job to create self-service payslips for each payee.

If ePay is not licensed, this process will report that ePay has not been licensed and will complete with success.

See Also

PeopleSoft Enterprise ePay 9.1 PeopleBook, "Managing Pay Information for Global Payroll," Setting Up View Payslip

Common Elements Used in This Chapter

Sequence	Determines the order in which the payslip elements appear. They appear in ascending order.
Element Name	The earning, deduction, or absence element name from its name page in its respective component.

Creating Payslip Templates

To create payslip templates, use the Templates HKG (GPHK_PSLP_SETUP) component.

This section provides an overview of payslip templates and discusses how to:

- Set up payslip templates and accumulators.
- Set up payslip earnings and deductions.
- Set up payslip absence details.

Understanding Payslip Templates

When designing payslips, you can:

- Set the accumulator column labels.
- Select the accumulators to appear under the column labels.
- Create unlimited numbers of rows of accumulators and set the sequence in which they appear.
- Create unlimited sections for earnings and deductions.
- Select the absence types that appear.
- Use standard or customized element descriptions.
- Set delivery options.

- Exclude departments or locations from printing at setup level, but override those exclusions at run time.

Pages Used to Create Payslip Templates

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Accumulators	GPHK_PSLP	Set Up HRMS, Product Related, Global Payroll & Absence Mgmt, Payslips, Templates HKG, Accumulators	Set up delivery and print exclusion options, column headings (labels), and column contents (rows of accumulators).
Earnings and Deductions	GPHK_PSLP1	Set Up HRMS, Product Related, Global Payroll & Absence Mgmt, Payslips, Templates HKG, Earnings and Deductions	Create sections of earnings and deductions, select from three description options, and set the element components (from the calculation rule) that the payslip displays.
Absence Details	GPHK_PSLP2	Set Up HRMS, Product Related, Global Payroll & Absence Mgmt, Payslips, Templates HKG, Absence Details	Add absence entitlements and absence pro rata elements. The payslip displays the current balance of the entitlement or pro rata.

Setting Up Payslip Templates and Accumulators

Access the Accumulators page (Set Up HRMS, Product Related, Global Payroll & Absence Mgmt, Payslips, Templates HKG, Accumulators).

Accumulators

Earnings and Deductions

Absence Details

Payslip ID: KHHKG01

Payslip Template Definition

Find | View All | First | 1 of 1 | Last

*Effective Date: 01/01/2000

*Description: Sample Payslip

Short Description: Sample Pay

*Delivery Option: Home Address

*Exclude Printing: None

Department List

Location List

Accumulator Labels

Column 1	Column 2	Column 3	Column 4	Column 5	Column 6
GROSS	NET				

Accumulator Elements

Customize | Find | First | 1-2 of 2 | Last

Accumulators 1 to 3

Accumulators 4 to 6

Sequence	Description	*Accumulator 1	*Accumulator 2	*Accumulator 3		
1	Pay Period	GROSS	NET		+	-
2	Year To Date	YTD AC EARNING	YTD AC NET		+	-

Accumulators page

Note. Select the tabs that are in the scroll area to access additional views of this page. Fields that are common to all views are documented first.

Payslip ID

Select an ID to attach a single template to multiple pay groups.

Note. Only one template can be attached to a pay group at one time.

Payslip Template Definition

Delivery Option

Determines where the hardcopy payslips are sent. Select from a list of internal type addresses, such as department or location, or external addresses, such as home address and mail address, which are recorded in the payee's personal data record.

Note. Use the Payslip Delivery Option HKG page to override the delivery destination of the printed payslip from the default delivery option that you select here. The Payslip Delivery Option HKG page is effective-dated to enable you to override the delivery option for a period of time.

Exclude Printing, Department List, and Location List

Select *Location* or *Department* to exclude the printing of specific departments or locations on your payslips. The corresponding links then become available and enable you to select the specific departments or locations that you don't want to display on the payslips during the print process. You can select multiple locations or departments.

If you want to print a location or department that you previously excluded, you can override this on the Create/Print Payslips HKG page before you run the print process.

Note. If you enter a pay entity as the reprint option on the Create/Print Payslips HKG page and you exclude a location that is part of that pay entity, it is not printed.

Accumulator Labels

Enter the column heading labels for the accumulators that appear across the page on the printed payslip.

Accumulators 1 to 3 Tab

Access the Accumulators 1 to 3 tab.

Sequence	Enter a sequence number to set the order in which the accumulators appear. They appear in ascending order.
Description	Enter a description of each accumulator row.
Accumulator 1, Accumulator 2, and Accumulator 3	<p>Select the accumulators to display for the corresponding column. Accumulator 1 values appear under the column 1 label, accumulator 2 values appear under the column 2 label, and so on.</p> <p>For example, you might have already have entered a description of sequence 1 and 2 as current and year to date. If you also want to display quarter-to-date accumulated amounts, you must create a new row, give the new row the description value of <i>QTD</i>, and select the accumulators that correspond to the column headings (labels).</p>

Accumulators 4 to 6 Tab

Access the Accumulators 4 to 6 tab.

Set up accumulators 4 to 6 on this tab. This is the same as the Accumulators 1 to 3 tab, except that it doesn't have sequence or description fields because the same sequence number and description apply to all six accumulators in the row.

Accumulators on Printed Payslips

The following diagram shows how column labels, sequences descriptions, and accumulator numbers work together on the printed payslip:

	Column 1 Label	Column 2 Label	Column 3 Label	Continued
Seq 1 Description	Accum 1, Seq 1	Accum 2, Seq 1	Accum 3, Seq 1	
Seq 2 Description	Accum 1, Seq 2	Accum 2, Seq 2	Accum 3, Seq 2	
Seq 3 Description	Accum 1, Seq 3	Accum 2, Seq 3	Accum 3, Seq 3	
Continued				

Columns and rows on the payslip in the Pay Summary region

See Also

Chapter 10, "Printing and Viewing Payslips," Overriding Payslip Delivery Options, page 117

Setting Up Payslip Earnings and Deductions

Access the Earnings and Deductions page (Set Up HRMS, Product Related, Global Payroll & Absence Mgmt, Payslips, Templates HKG, Earnings and Deductions).

Accumulators Earnings and Deductions Absence Details

Payslip ID: KHHKG01

Payslip Template Definition Find | View All First 1 of 1 Last

Effective Date: 01/01/2000 Description: Sample Payslip Short Description: Sample Pay + -

Section Setup Find | View All First 1 of 3 Last

Sequence: 1 Description: EARNINGS ☐ MPF Section + -

Sections Elements Customize | Find | First 1-22 of 22 Last

Element Details Element Components

Sequence Number	Element Name	Display YTD Units	Display YTD Amount		
1	BASSAL	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	+	-
2	BASHLY	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	+	-
3	OT1.5	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	+	-
4	OTFIX	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	+	-
5	SHNT1.3	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	+	-
6	SHNTFIX	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	+	-
7	TYPHOON	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	+	-
8	BLCKRAIN	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	+	-
9	MEAL	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	+	-
10	MOBILE	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	+	-
11	HSING	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	+	-
12	GRA	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	+	-
13	13MTHPAY	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	+	-
14	CASHADV	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	+	-
15	MEALREIM	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	+	-

Earnings and Deductions page: Element Details tab

Common Page Elements

Description

You can create and name an unlimited number of sections. Create each section by entering a sequence number for it and a name, such as earnings.

You can determine the sequence for the individual earning and deduction elements that appear under these sections.

MPF Section (mandatory provident fund section)

Select to display the following mandatory provident fund (MPF) details on payslips:

- Employer mandatory contribution period.
- Employee mandatory contribution period.
- Total base on which MPF was calculated.
- Contribution pay date to trustee.

All of the related information is stored and retrieved from the MPF result table (GPHK_MPF_RSLT).

Element Details Tab

Access the Element Details tab.

<p>Display YTD Units (display year-to-date units) and Display YTD Amount(display year-to-date amount)</p>	<p>Select these check boxes to have the year-to-date units and amounts for each element appear in the payment details region under the heading <i>Year to Date Values</i>.</p>
---	--

Element Components Tab

Access the Element Components tab.

<p>Description Type and Description</p>	<p>You can create a custom description of each element. Select the following values for each element:</p>
--	---

Custom: A field becomes available that enables you to change the default name of the element. For example, *Basic Salary 1*.

Description: The default element description appears. For example, *Basic Salary*.

Element Name: The default system element name appears. For example, *BASSAL*.

Print Base, Print Percentage, Print Rate, and Print Unit

These check boxes represent the components of the calculation rule for the element. Select the components to show for each earning or deduction on the component. You can select only the components that are in the calculation rule for the element. For example, for earnings with the calculation rule (unit) × (rate), only the unit and rate check boxes are available for entry.

If the component is not in the calculation, the check box is cleared and unavailable for selection.

Note. The amount always appears, so it isn't an option here.

Setting Up Payslip Absence Details

Access the Absence Details page (Set Up HRMS, Product Related, Global Payroll & Absence Mgmt, Payslips, Templates HKG, Absence Details).

Payslip ID: KHHKG01

Payslip Template Definition Find | View All | First | 1 of 1 | Last

Effective Date: 01/01/2000 **Description:** Sample Payslip **Short Description:** Sample Pay

Absence Setup Customize | Find | First | 1-3 of 3 | Last

Element Details

*Sequence	Element Name	*Description Type	Description
1	ALV GENL ENT	Description	Genl Annual Leave Entitlement
2	ALV STAT ENT	Description	Stat Annual Leave Entitlement
3	SLV SICK ENT	Description	Sick Leave Entitlement

Absence Details page

Select the absence elements to display in the absence section of the payslip and the sequence in which these elements appear.

Use this page the same way that you use the Earnings and Deduction page. Enter a sequence number and an element name, and select one of three descriptions.

Attaching Payslip Templates to Pay Groups

To attach payslip templates to pay groups, use the Link to Pay Group HKG (GPHK_PYGRP_PSLP) component.

This section discusses how to attach payslip IDs to pay groups.

Page Used to Attach Payslip Templates to Pay Groups

Page Name	Definition Name	Navigation	Usage
Link to Pay Group HKG	GPHK_PYGRP_PSLP	Set Up HRMS, Product Related, Global Payroll & Absence Mgmt, Payslips, Link to Pay Group HKG, Link to Pay Group HKG	Attach the payslip template to pay groups.

Attaching Payslip IDs to Pay Groups

Access the Link to Pay Group HKG page (Set Up HRMS, Product Related, Global Payroll & Absence Mgmt, Payslips, Link to Pay Group HKG, Link to Pay Group HKG).

Link to Pay Group HKG

Pay Group:

G1BNK01

Banking Interfaces Test Paygro


Effective Date:

01/01/2004

Payslip Template

Payslip ID:

KHHKG01



Sample Payslip

Link to Pay Group HKG page

Payslip ID

After you create the payslip, attach the template to pay groups.

Note. You can only attach one template to a pay group at one time.

See Also

[Chapter 5, "Setting Up Payslips," Creating Payslip Templates, page 36](#)

Creating Payslip Messages

To create payslip messages, use the Messages HKG (GPHK_PSLP_MSG) component.

This section discusses how to create payslip messages.

Page Used to Create Payslip Messages

Page Name	Definition Name	Navigation	Usage
Messages HKG	GPHK_PSLP_EXT	<ul style="list-style-type: none">Set Up HRMS, Product Related, Global Payroll & Absence Mgmt, Payslips, Messages HKG, Messages HKGGlobal Payroll & Absence Mgmt, Payslips, Add Payslip Messages HKG, Messages HKG	Create payslip messages and control who receives the messages.

Creating Payslip Messages

Access the Messages HKG page (Set Up HRMS, Product Related, Global Payroll & Absence Mgmt, Payslips, Messages HKG, Messages HKG).

Messages HKG page

You can configure text messages that appear on payslips and select the recipient level to which the message is distributed. You can select the following recipient levels:

- All employees who are identified in the calendar group.
- All payees who are associated with a group build ID.
- Employees who are in a specific employee list.

Message Number

Enter the message ID that the system uses to receive the correct message for the correct payees. Arrays and formulas combine to retrieve the correct message. You can enter multiple numbers for multiple messages.

Message Level and Group ID

Select the recipient of the message:

All: All payees that are identified in the calendar group.

Group: All payees that are included in a group that is built by using the Group Build Definition feature in Human Resources (called VC Group Build in Variable Compensation). If you select this value, the Payee Message link becomes unavailable for selection and you can select a group ID.

The HK AR GRP BLD ID array extracts all employees that exist for the group build ID that might also exist for the calendar group ID. This array uses the processing formula HK FM GRP BLD ID. The array extracts all employees from the Group Build result table (GB_GRP_RES_TBL).

Group List: All payees that are in a list that is built by using the Global Payroll Group List feature. If you select this value, the Payee Message link becomes available for selection.

Message

Enter the text of the message that is to appear on selected payslips.

Note. The HK AR PSLP MSG writable array extracts the payslip message level and message. It uses the processing formula HK FM PSLP MSG, which retrieves the correct message for the correct calendar group ID. This array extracts all fields from the payslip message record (GPHK_PSLP_MSG) and writes the message to the writable array result table (GPHK_PSLP_RSLT). The writable array stores data from certain system elements, such as the pay period to and from dates and payslip messages.

Chapter 6

Defining Earnings

This chapter provides overviews of earnings in Hong Kong, subsetting, and delivered earning elements, and discusses how to:

- Calculate basic salary earnings.
- Calculate basic hourly earnings.
- Calculate overtime earnings.
- Calculate shift allowance earnings.
- Calculate typhoon and black rain allowances.
- Calculate meal allowances.
- Calculate meal reimbursement.
- Calculate mobile phone and pager allowances.
- Calculate housing allowance.
- Calculate rent reimbursement.
- Calculate education allowances.
- Calculate gratuity earnings.
- Calculate the thirteenth month pay.
- Calculate cash advances.
- Calculate absence and termination earnings.
- Calculate amount earnings.
- Calculate Mandatory Provident Fund (MPF) earnings.
- Calculate rolling average earnings.
- Control the maximum frequency amount.
- Control earnings maximum or goal amount.
- Schedule earnings using generation control.

Understanding Earnings in Hong Kong

PeopleSoft has created several earnings to demonstrate the flexibility of the Global Payroll rules to meet common processing requirements. The following sections discuss:

- Ways that you can use earning and supporting elements to produce the desired results.
- How PeopleSoft meets specific earning processing requirements.

Note. User keys enable you to track an accumulator at levels lower than the employee record. This directs the system to maintain different accumulated numbers for each of the employee's locations. User key 1 for all earnings on the Earnings Accumulators page is PAY ENTITY. (This is required by Inland Revenue Reporting.) User key 2 for all year-to-date accumulators is CM VR BAL GRP ID (balance group ID).

See Also

PeopleSoft Enterprise Global Payroll 9.1 PeopleBook, "Defining Earning and Deduction Elements"

Viewing Delivered Elements

The PeopleSoft system delivers a query that you can run to view the names of all delivered elements designed for Hong Kong. Instructions for running the query are provided in the *PeopleSoft Enterprise Global Payroll 9.1 PeopleBook*.

See Also

PeopleSoft Enterprise Global Payroll 9.1 PeopleBook, "Viewing Delivered Elements," Understanding How to View Delivered Elements

Understanding Subsetting

Subsetting enables a group of earnings to be paid for a calendar. For example, during a regular calendar run, you commonly pay basic salary and other earnings. In a 13th month off-cycle calendar run, you are required to pay only 13th month pay.

A variable is overridden at the calendar level. The variable contains the subset type. A formula determines whether the variable is for a subset type such as 13th month pay. The formula is attached to the process list condition and the section resolves if the formula is true.

The 13th month pay formula CM FM 13MTH SUBSET resolves if the variable CM VR SUBSET TYPE is 13MTH (for 13th month pay).

The variable CM VR SUBSET TYPE stores the calendar subset type. You attach the variable on the calendar override page and assign it the appropriate run. The variable is used in a section conditional formula to resolve the section based on the calendar. For example, to run a regular subset type, assign the value REGULAR to the variable. If you run an off-cycle 13th month pay run, assign the value 13 MONTH to the variable. Only the 13th month section is resolved.

See Also

Chapter 6, "Defining Earnings," Calculating the Thirteen Month Pay, page 58

Understanding Delivered Earning Elements

In the following table, the first column combines the earning's name and description. A (GC) in the row indicates that the earnings have a generation control. The other four columns indicate the earning calculation rule of Unit \times Rate, Unit \times Rate \times Percent, or Amount. The formulas used for some of the earnings are discussed in further detail. (SE) indicates a system element, and (N) indicates numeric.

Name and Description	Unit	Rate	Base	Percent	Amount
Regular Pay					
BASSAL Basic salary					COMPRATE
BASHLY Basic hourly	Payee Level	HOURLY RT (SE)			
Overtime					
OT1.5 Overtime 1.5 \times	Payee Level	HOURLY RT (SE)		150	
OTFIX Overtime fix	Payee Level	200 (N)			
Shifts					
SHNT1.3 Shift 1.3 \times	Payee Level	HOURLY RT (SE)		130 (N)	
SHNTFIX Shift fix	Payee Level	200 (N)			

Name and Description	Unit	Rate	Base	Percent	Amount
Allowances					
TYPHOON Typhoon allowance	Payee Level	HOURLY RT (SE)		200 (N)	
BLCKRAIN Black rain allowance	Payee Level	HOURLY RT (SE)		200 (N)	
MEAL Meal allowance					2000 (N)
MEALREIM Meal reimbursement					Payee Level
MOBILE Mobile and pager allowance (GC)					250 (N)
HSING Housing allowance					ALW FM HOUSING
RENTREIM Rent reimbursement					Payee Level
EDALLOW Education allowance (GC)					Payee level
GRA Gratuity (GC)					Payee Level
13MTHPAY 13th month payment (GC)			OE FM 13MTH BASE	100 (N)	
CASHADV Cash advance (GC)			BASSAL	Payee Level	

Name and Description	Unit	Rate	Base	Percent	Amount
Leave (Absence)					
DY WAGE 80 80 percent of daily wages	Payee Level	CM FM DAILY WAGE		80 (N)	
LWOP Leave without pay	Payee Level	DAILY RT (SE)		80 (N)	
LWOP2 Leave without pay for hourly rates	Payee Level	HOURLY RT			
SEV/LSP Severance and long service					TER FM LSP PAYMT
Termination					
ANN LIEU Annual leave in lieu	TER FM ALV BAL	CM FM DAILY WAGE			
TER 13TH PAY 13th payment termination			TER FM 13TH PAY	100 (N)	

Calculating Basic Salary Earnings

Basic salary (BASSAL) is an earning element with a flat amount that is paid at the earning's level only. Basic salary is paid once per month for permanent employees, in the first month for new hires, and in the last month for terminated employees.

The calculation rule is Amount which is the system element COMPRATE—the payee's monthly compensation rate.

The system uses pay group proration whenever there is a partial period or when a pay rate change occurs during the pay period. Following are examples of the partial basic salary earning calculation:

Example 1

An employee is hired on February 20, 2000 with a salary of 1000 HKD. The basic salary is calculated as:

$$10 / 29 \times 1000 = 344.83$$

Example 2

If an employee salary increases to 1200 HKD effective March 18, 2000, then the March basic salary is calculated as:

$$(17 / 31 \times 1000) + (14 / 31 \times 1200) = 548.39 + 541.94 = 1090.33$$

Calculating Basic Hourly Earnings

Basic hourly earning (BASHLY) is the monthly income for hourly employees. It is paid once per pay period to the entire hourly pay group. The system uses the hourly rate to calculate monthly income for hourly employees.

The calculation rule is $\text{Unit} \times \text{Rate}$:

- Unit is the number of hours worked.
- Rate is the system variable HOURLY RT.

Hourly rate is calculated from the employee's compensation rate. The number of hours is entered at the positive input level. When a pay rate change occurs during the pay period, the system variable returns the correct hourly rate.

Calculating Overtime Earnings

Two earning elements exist for overtime:

- OT1.5 calculation rule is used to pay time-and-a-half.
- OT FIX calculation rule is used to pay a fixed amount of 200 HKD.

OT1.5 Calculation Rule

The overtime rate is 1.5 times the standard hourly rate.

The OT1.5 calculation rule is $\text{Unit} \times \text{Rate} \times \text{Percent}$:

- Unit is the number of overtime hours at the payee level.
- Rate is the system variable HOURLY RT.
- Percent is 150.

Example

If an employee worked 7.5 overtime hours and the standard hourly rate is 400 HKD, the overtime payment is calculated as:

$$7.5 \times 1.5 \times 400 = 4500$$

OT FIX Calculation Rule

Employees who work overtime and leave the office after 21:00 hours are paid a fixed amount of 200 HKD.

The OT FIX calculation rule is Unit \times Rate:

- Unit is the number of days that the employee worked overtime and left after 21:00 hours, determined at the payee level.
- Rate is a fixed numeric value of 200 HKD.

Example

If an employee worked three days overtime and left the office after 21:00, the overtime payment is calculated as:

$$3 \times 200 = 600$$

Enter unit amounts for overtime earnings using positive input. In Hong Kong, the previous month's overtime payment might be paid in the current month. When the pay date is a few days before the pay period end date, the overtime hours between the pay date and pay period end date are unknown. Consequently, when overtime earnings for a previous month are paid in the current period, the system treats it as retroactive pay.

Calculating Shift Allowance Earnings

Two earnings for shift allowances are paid once per month to compensate employees who work overnight. Like overtime, there is an earning element to pay a fixed amount (SHNTFIX) and another to pay 130 percent of the hourly rate (SHNT1.3). This section discusses how to:

- Calculate SHNTFIX earnings.
- Calculate SHNT1.3 earnings.

Calculating SHNTFIX Earnings

The SHNTFIX calculation rule is Unit \times Rate:

- Unit is the number of overnight shifts that the payee worked.
- Rate is a fixed numeric value of 100 HKD.

Calculating SHNT1.3 Earnings

The SHNT1.3 calculation rule is $\text{Unit} \times \text{Rate} \times \text{Percent}$:

- Unit is the number of overnight shifts that the payee worked.
- Rate is the system variable HOURLY RT.
- Percent is 130.

Calculating Typhoon and Black Rain Allowances

Typhoon (TYPHOON) and black rain (BLCKRAIN) allowances are intended to compensate employees for inconveniences caused by typhoons or black rain duty. Both typhoon and black rain compensations are paid monthly. This section discusses how to:

- Calculate TYPHOON allowances.
- Calculate BLCKRAIN allowances.

Calculating TYPHOON Allowances

The TYPHOON calculation rule is $\text{Unit} \times \text{Rate} \times \text{Percent}$:

- Unit is the number of hours that the employee worked during a typhoon advisory.
- Rate is the system variable HOURLY RT.
- Percent is 200.

Calculating BLCKRAIN Allowances

The BLCKRAIN calculation rule is $\text{Unit} \times \text{Rate} \times \text{Percent}$:

- Unit is the number of hours that the employee worked during a black rain advisory.
- Rate is the system variable HOURLY RT.
- Percent is 200.

Calculating Meal Allowances

A fixed meal allowance (MEAL) of 2000 HKD is defined at the earning assignment level as a recurring payment and paid each month to employees in the salary pay group.

The MEAL calculation rule is Amount:

Amount is fixed at 2000 HKD.

Calculating Meal Reimbursement

Meal reimbursement (MEALREIM) is a nontaxable meal expense. You can set the maximum claiming limit for every claim.

The calculation rule is Amount:

Amount is established at the payee level using positive input.

While meal reimbursement (MEALREIM) has no minimum amount limit, it does have a maximum limit of 100 HKD per claim. Therefore, for every claim, you can reimburse the lower of 100 HKD or the exact expense from the bill to the employee. Each month can have multiple instances of claims. The total amount of monthly claims is paid as part of the monthly salary.

Example

Following is a simple example with one positive input instance of 110 HKD. If an employee is paid 110 HKD, but the maximum earnings limit is 100 HKD, the system pays 100 HKD. If the 110 HKD payment is spread over multiple positive input instances, the system still compares it to the paid sum.

In this case, the system determines whether the accumulated monthly amount exceeds the monthly maximum amount of 100 HKD. The system displays a warning message and pays only 100 HKD, because 110 HKD is greater than 100 HKD.

With multiple positive input (PI) instance paid:

<i>PI Instance</i>	<i>Amount HKD</i>	<i>Accumulator HKD</i>	<i>< or > HKD</i>	<i>Resolve HKD</i>
1	40	40	< 100	40
2	40	80	< 100	40
3	40	120	> 100	20

While the system pays PI instance 1 and 2, PI instance 3 exceeds the maximum amount by 20 HKD. In this case, the system resolves 20 HKD for PI instance 3.

Depending on the frequency, the maximum amount is converted to the calendar period maximum amount (monthly or annual frequency). For example, if you select a frequency of annual, the process deannualises the maximum amount.

The formula FM MAX AMT determines whether the earning accumulated amount exceeds the maximum. The accumulated amount is used is because the system must calculate the total amount paid through positive input.

Calculating Mobile Phone and Pager Allowance

MOBILE is a nontaxable expense for using mobile phones or pagers.

The calculation rule is Amount:

Amount is a fixed numeric value of 250 HKD.

The mobile and pager allowance is 250 HKD per month, payable at the earning's level for the salaried pay group.

The generation control CM GC RSLV ONCE stops the allowance from resolving twice if period segmentation occurs.

Calculating Housing Allowances

The housing allowance (HSING) is a monthly taxable benefit.

The calculation rule is Amount:

Amount is set by the formula ALW FM HOUSING.

Working with the ALW BR HOUSING Bracket

This section discusses how to work with ALW BR HOUSING bracket.

This HSING earning element pays the housing allowance. The amount depends on the payee's salary grade. The ALW BR HOUSING bracket stores the salary grade and the corresponding housing allowance amount.

Example

A Grade 001 payee is paid 10000 HKD and a Grade 003 payee is paid 5000 HKD. The ALW BR HOUSING bracket stores the following information:

Salary Grade	Monthly Housing Allowance
001	10,000
002	8000
003	5000
004 or lower	NA (ineligible)

This customary bracket enables you to update or add additional grades and allowance amounts. The system compares the payee's salary grade to the ALW BR HOUSING bracket and pays the corresponding allowance. If the payee's salary grade is not found, the system pays a zero allowance. The earnings are paid at the earning assignment level because it is a recurring monthly payment.

Note. Only employees in the salaried pay group are eligible for this benefit.

Calculating Rent Reimbursement

Rent reimbursement (RENTREIM) is used to pay an employee's accommodation costs when working far from home.

The calculation rule is Amount:

Amount is entered through positive input at the payee level.

This earning element has no maximum amount limit. When the employee's claim is approved, the employee receives the rent reimbursement in the current pay period.

Note. Employees can have one rent reimbursement per month. Multiple instances are not allowed.

Calculating Education Allowances

Your organisation might set up scholarship programs for employees. The education allowance (EDALLOW) is paid once per year. This fixed scholarship amount is granted to employees when their dependent receives an offer from the recognized institute.

The calculation rule is Amount:

Amount is set at the payee level through positive input.

Employees can apply for the education allowance again in future academic years. No refund is made when their dependents drop out of a course, or if the employee is terminated.

Because the education allowance is paid as a flat amount and as a recurring override, you can enter the amount at the payee earning assignment level. The reason for this is that the education allowance is paid when the scholarship is granted.

The generation control CM GC RSLV ONCE ensures that the allowance is paid only once per year if period segmentation occurs.

Calculating Gratuity Earnings

Gratuity (GRA) is a single payment to contract workers at the end of a contract or when a contractor leaves.

The calculation rule is Amount:

Amount is set at the payee level.

This section discusses how to:

- Use generation control in gratuity calculation.
- Use formulas in gratuity calculation.

Using Generation Control in Gratuity Calculation

Gratuity is paid to employees working on contract by using the generation control OE GC GRA. The system automatically pays gratuity based on the contract end date and resolves the amount using the generation control. When the employee is unable to finish the contract, the amount of the gratuity is prorated. No proration rule applies because of the many ways gratuity can be paid in Hong Kong. It is up to the organisation to pay prorated gratuity when contract employees cannot finish the contract period.

While you enter gratuity at the earning assignment level, it is resolved once through generation control.

Using Formulas in Gratuity Calculation

Gratuity earnings resolve if the contract end date occurs during the current pay period. If the contract end date is outside the current pay period, the gratuity is not paid. The OE FM CNTR EXPIRE formula determines whether the contract end date occurs during the current pay period and uses segment begin and end date so that the earnings are not paid twice during period segmentation.

Calculating the Thirteen Month Pay

It is common in Hong Kong to pay employees an extra month of basic salary. The system pays the basic salary as of the last period of the last calendar year. The 13MTHPAY earning element is payable only on the Chinese New Year. For example, the Chinese New Year off-cycle run is during either January or February, but basic salary is paid as of December of the last calendar year.

The calculation rule is $\text{Base} \times \text{Percent}$:

- Base is set by the formula OE FM 13MTH BASE (base pay).
- Percent is 100.

Understanding 13th Month Pay Proration

This section discusses the 13th month pay proration.

Proration applies to 13th month pay. The proration calculates the employee's total days of service divided by the number of days in a calendar year.

If the employee's hire date is before the start of the last calendar year, then no proration occurs. If the employee's hire date is after the start of the last calendar year, proration is calculated as follows:

The following system parameters are considered in the payment calculation:

Prorated 13th month pay is paid if the permanent employee has worked fewer than twelve months. The following system parameters are considered in the payment calculation:

- Factor: 100 percent of basic salary.
- Salary day: December 31, 2000.
- Cut off day: November 1, 2000.
- Proration rule: (Service period in year) / (Calendar days in year) × basic salary.

Example 1: Receiving the Full Factor

An employee is hired on February 2, 1999. Their basic salary as of December 31, 2000 is 12000 HKD. The employee's 13th month pay = 12000 HKD.

Example 2: Employee Joins After Cut-off Day

An employee is hired on November 1, 2000. Their basic salary as of December 31, 2000 is 20000 HKD. The employee's 13th month pay is zero.

Example 3: Proration Rule Applied

An employee is hired on January 10, 2000. Their basic salary as of December 31, 2000 is 30000 HKD. The employee's 13th month pay is calculated as:

$$(357 / 366) \times 30000 = 29262.30$$

Note. Terminated employees are eligible for prorated 13th month pay only if they have completed their probation period.

Using Generation Control in the 13th Month Pay Calculation

Generation control OE GC 13MTH PAY is used to resolve the earnings based on the cut-off date. The cut-off date is entered at the pay group override level. The earnings are paid through earning assignment with begin and end dates so that they are paid once during the Chinese New Year.

See Also

Chapter 13, "Defining Absence Rules," Calculating 13th Month Payment, page 148

Calculating Cash Advances

An employee can be paid a cash advance of 50 percent of basic salary (CASHADV), which one must pay back in installments over five months.

The calculation rule is Base × Percent:

- Base is the earning element BASSAL—base salary.
- Percent is set at the payee level.

The generation control CM GC RSLV ONCE prevents the allowance from being paid more than once if period segmentation occurs. Generation control also ensures that the allowance is paid only once per year.

Note. The CASHADV deduction with the formula DED FM CASHADV that calculates 20 percent of the goal amount enables the employee to pay back the cash advance.

See Also

Chapter 7, "Defining Deductions," Calculating Cash Advance Recovery, page 74

Calculating Absence and Termination Earnings

This section discusses how to:

- Calculate annual leave instead of annual leave entitlement.
- Calculate eighty percent of daily wages.
- Calculate leave without pay (LWOP and LWOP2).
- Calculate severance and long service payments (LSP).
- Calculate thirteenth month payment on termination.

Calculating Annual Leave Instead of Annual Leave Entitlement

The ANN LIEU is a payment in lieu of annual leave entitlement. This earning element is used to pay terminated employees for unused annual leave or for part of their annual leave entitlement before the leave is forfeited.

The calculation rule is $\text{Unit} \times \text{Rate}$:

- Unit is set by the formula TER FM ALV BAL.
- Rate is set by the formula CM FM DAILY RATE.

ANN LIEU is a taxable earning element, which means that it contributes to the annual taxable accumulator. ANN LIEU is also used to pay employees when they accept the payment from their employer to offset part of their annual leave. This is a positive input and the unit of ANN LIEU is overridden by the number of adjusted days from the annual leave balance.

Note. ANN LIEU can be a negative value because general employees in Hong Kong are allowed to have a negative balance.

See Also

[Chapter 13, "Defining Absence Rules," Calculating Annual Leave, page 144](#)

[Chapter 13, "Defining Absence Rules," Calculating Unused Annual Leave, page 147](#)

Calculating 80 Percent of Daily Wages

The DY WAGE 80 earning element is 80 percent of average earnings paid to statutory employees when taking maternity leave or sick leave. Employees are eligible for maternity leave payments after 40 weeks of continuous service. The entitlement is granted when the leave occurs and the paid maternity period is 70 days from the maternity commencement date. The absence period can be shorter but not longer than 70 days. Unpaid maternity is treated as LWOP.

The calculation rule is $\text{Unit} \times \text{Rate} \times \text{Percent}$:

- Unit is set at the payee level.
- Rate is set by the formula CM FM DAILY WAGE.
- Percent is 80.

Note. 80 percent of an employee's daily wage is covered for valid maternity leave for statutory employees and 100 percent coverage for general employees.

See Also

[Chapter 13, "Defining Absence Rules," Calculating Sick Leave, page 151](#)

[Chapter 13, "Defining Absence Rules," Calculating Maternity Leave, page 152](#)

Calculating Leave Without Pay (LWOP)

The total LWOP ($\text{Units} \times \text{Daily Rate}$) is subtracted from an employee's basic salary if the employee takes leave without pay.

The calculation rule is $\text{Unit} \times \text{Rate}$:

- Unit is set at the payee level.
- Rate is the system variable DAILY RT.
- Percent is 80.

Note. The LWOP earning element is used for salary based employees. The LWOP2 earning element is used by weekly employees as it uses an hourly rate.

See Also

Chapter 13, "Defining Absence Rules," Calculating Leave Without Pay, page 153

Calculating Leave Without Pay (LWOP2)

The LWOP2 earning element is used for leave without pay for hourly rates (for weekly employees— as it uses an hourly rate).

The calculation rule is $\text{Unit} \times \text{Rate}$:

- Unit is set at the payee level.
- Rate is the system variable HOURLY RATE.

Note. To be able to use the LWOP2 earning and absence take correctly, you have to deselect the eligibility for positive input check box. If you do not do this, LWOP and LWOP2 will both be processed for an employee. An employee can only receive one or the other, depending on their eligibility.

See Also

Chapter 13, "Defining Absence Rules," Calculating Leave Without Pay, page 153

Calculating Severance and Long Service Payments

Terminated employees might have severance (SEV) or long service payments (LSP), but not both. The SEV/LSP earning element is processed in the TER SE MAIN section and is a nontaxable payment. An employer should pay severance when an employee who has been employed under a continuous contract for no fewer than 24 months is dismissed by reason of redundancy. An employer should pay long service payments when an employee has been employed no fewer than five years under a continuous contract.

The calculation rule is Amount:

Amount is set by the formula TER FM LSP PAYMT.

The variable TER VR LSP CEILING stores the maximum ceiling of average wages which is currently 15000 HKD.

The variable TER VR MAX LSP stores the maximum LSP amount used in the bracket.

The formula TER FM LSP PERIOD is used as the search key of the bracket TER BR LSP ENT.

The bracket TER BR LSP ENT stores the list of years of service and maximum claimable LSP amounts.

See Also

Chapter 13, "Defining Absence Rules," Calculating Severance and Long Service Leave Payments, page 149

Calculating 13th Month Payment on Termination

If an employee is eligible for 13th month pay and is terminated after three months of continuous service, prorated 13th month pay is paid when the employee is terminated. The TER 13TH PAY earning element is used to pay the 13th month payment for terminated employees.

The calculation rule is Base \times Percent:

- Base is set by the formula TER FM 13TH PAY.
- Percent is 100.

The prorated 13th month payment calculation is:

$(\text{Duration between service date and termination date}) / 365 \times (\text{monthly rate})$

If the employee received current year 13th month pay before Chinese New Year, (terminated on June 2000) and received 13th month pay in February 2000, the prorated 13th month payment is calculated as:

$(\text{Duration between January 1, 2000 and termination date}) / 365 \times (\text{monthly rate})$

Factor 365 is used even in a leap year.

Note. The 13th MTH PAY is different from the TER 13TH PAY (termination) earning element. The 13th MTH PAY earning element is the calculation of the regular year end. TER 13TH PAY is used exclusively for the TER SE MAIN termination section.

See Also

Chapter 13, "Defining Absence Rules," Calculating 13th Month Payment, page 148

Chapter 13, "Defining Absence Rules," Calculating Absence Entitlements on Termination, page 147

Calculating Amount Earnings

This section discusses:

- Flat amounts.
- Formula-based amounts.

Flat Amounts

For Hong Kong, there are eight earnings with the calculation rule Amount. Two are flat amounts:

- Meal allowance (MEAL).
- Mobile and pager (MOBILE).

See Also

[Chapter 6, "Defining Earnings," Calculating Meal Allowances, page 54](#)

[Chapter 6, "Defining Earnings," Calculating Mobile Phone and Pager Allowance, page 56](#)

Formula-Based Amounts

The housing allowance uses the ALW FM HOUSING formula to find the earning amount that stores the salary grade and the corresponding housing allowance amount.

The gratuity earnings use the formula OE FM CNTR EXPIRE to determine whether the contract dates occur during the current pay period and use segment begin and end dates so that the earnings are not paid twice in period segmentation.

The termination earnings use formula OE FM ROLL AVG to calculate the rolling average amount. The formula calls a historical rule to retrieve the amount from an accumulator. The formula then calculates the average from the amount retrieved.

The severance and long service leave earnings use formula TER FM LSP PAYMT to return the severance payment or long service payment, depending on the year of service and the action reason.

See Also

[Chapter 6, "Defining Earnings," Calculating Housing Allowances, page 56](#)

[Chapter 6, "Defining Earnings," Calculating Gratuity Earnings, page 57](#)

[Chapter 6, "Defining Earnings," Calculating Absence and Termination Earnings, page 60](#)

[Chapter 6, "Defining Earnings," Calculating Severance and Long Service Payments, page 62](#)

Calculating Mandatory Provident Fund Earnings

Not all earnings are included in Mandatory Provident Fund (MPF) calculations. Earnings that are included in the MPF calculation are considered relevant income and include wages, salaries, leave pay, fees, commissions, bonuses, and gratuities. Examples of earnings that are excluded from MPF calculations are housing allowances, housing benefits, severance payments, and long service leave payments. The following earnings are included as relevant earnings in MPF calculations:

<i>Name of Earning</i>	<i>Description</i>
BASSAL	Basic salary
OT1.5	Overtime 1.5 ×

<i>Name of Earning</i>	<i>Description</i>
OTFIX	Overtime fix
SHNT1.3	SHIFT1.3 ×
SHNTFIX	Shift fix
GRAT	Gratuity
13MTHPAY	Thirteenth month pay
TYPHOON	Typhoon allowance
BLCKRAIN	Black rain allowance
MOBILE	Mobile and pager allowance
BASHLY	Basic hourly salary

These earnings are included in the monthly accumulator MPF AC REVLNT INCM that is based on the pay period end date and the user key of EmplID (employee identification).

See Also

Chapter 8, "Administering Mandatory Provident Fund Contributions," page 77

Calculating Rolling Average Earnings

This section provides an overview of rolling average earnings and discusses how to:

- Use accumulators in the rolling average calculation.
- Use variables in the rolling average calculation.
- Use formulas in the rolling average calculation.
- Work with rolling average (example).

Understanding Rolling Average Earnings

The earning rolling average is used to calculate compensation when there is a termination or accident at work. You can set up an earning element for which the rate is determined by the average of another earning element during a rolling period, such as the preceding 12 months.

The following earnings contribute to average earnings:

- Cash wages.
- The value of any privilege or benefit that can be estimated in cash (such as food, fuel, or quarters supplied to the employee).
- Overtime or other special remuneration through bonus, allowance, or otherwise.
- Customary tips.

Using Accumulators in the Rolling Average Calculation

The rolling average calculation uses the OE AC ROLLAVG AMT (amounts) accumulator. The accumulator accumulates the earnings listed in the following table for rolling average calculation. It is a monthly accumulator with an accumulated date of the payment date. The system uses the amount values of the members of accumulator OE AC ROLLAVG AMT in its averaging calculation. PeopleSoft delivers this accumulator with the following earnings as its members:

<i>Name of Earning</i>	<i>Description</i>
BASSAL	Basic salary
BASHLY	Basic hourly salary
OT1.5	Overtime 1.5×
OTFIX	Overtime fix
SHNT1.3	SHIFT1.3×
SHNTFIX	Shift fix
MEAL	Meal allowance
HSING	Housing allowance
GRAT	Gratuity

<i>Name of Earning</i>	<i>Description</i>
13MTHPAY	13th month pay

See Also

PeopleSoft Enterprise Global Payroll 9.1 PeopleBook, "Setting Up Accumulators"

Using Variables in the Rolling Average Calculation

The rolling average calculation uses the OE VR ROLLAVG AMT (amounts) variable. The system adds the amounts retrieved from the OE AC ROLLAVG AMT accumulator to variable OE VR ROLLAVG AMT. The variable OE VR ROLL UNIT holds the rolling number of months for calculating the rolling average. You can set the variable OE VR ROLL UNIT to the number of months that you want the system to use to retrieve period data for use in the calculation.

See Also

PeopleSoft Enterprise Global Payroll 9.1 PeopleBook, "Defining Calculation Elements," Defining Variable Elements

Using Formulas in the Rolling Average Calculation

The rolling average calculation uses the OE FM ROLLAVG AMT (amounts) formula. The rolling unit indicates how far back to calculate the rolling average. The formula OE FM ROLLAVG AMT, attached to an earning element, calls a historical rule to retrieve the accumulator value at the time of the calculated period. The period is calculated by the last period end date minus the number of months specified. The formula then calculates the average from the amount retrieved.

See Also

PeopleSoft Enterprise Global Payroll 9.1 PeopleBook, "Defining Calculation Elements," Defining Formula Elements

Working with Rolling Average (Example)

Following is an example of the accumulated value of the earning element for the last five periods. Assume that:

- In period 2, these earnings did not contribute to the accumulator.
- You are running the pay run in period 5.

Value	Period 1	Period 2	Period 3	Period 4	Period 5
Earnings value	10,000	Not paid	10,000	10,000	10,000
Accumulator Value	10,000	10,000	20,000	30,000	40,000

Assume that you want to calculate the average earnings for the last four periods from period 5 (hence, you retrieve from period 1). Therefore, the accumulator holds 10000 for period 1 and the rule retrieves 1,000. The formula retrieves the current period accumulator value of 40000 in period 5.

The rolling average calculation is as follows:

$((\text{Accumulator, current period}) - (\text{Accumulator, previous period})) / (\text{Months})$

Hence, the calculation resolves to:

$(40,000 - 10,000) / 4 = 7500$

Controlling the Maximum Frequency Amount

There is an accumulator for each monthly and annual frequency. You can select a frequency of monthly or annual. Two accumulators are provided for each frequency.

During the calculation process, a formula determines whether the accumulated amount exceeds the maximum. Depending on the frequency, the formula selects the appropriate accumulator.

You can set the maximum amount and frequency at the payee level. The earning element MEALREIM is set up this way. The accumulator CM AC MAX MONTH determines whether the monthly maximum amount (ceiling) has been reached for meal reimbursements.

Example 1

With a maximum yearly amount of 10040 HKD, the system pays 40 HKD if the payee's earnings are 50 HKD per month, and after payment, the accumulated yearly amount is 10050 HKD.

Example 2

With a monthly maximum amount of 60 HKD, the system pays 10 HKD if the payee's earnings are 50 HKD per month, and after payment, the accumulated monthly amount is 100 HKD. The system determines whether the accumulated monthly amount exceeds the monthly maximum amount of 60 HKD.

In this case, because 100 HKD is greater than 60 HKD, the accumulated monthly amount does exceed the monthly maximum amount. The earning amount is updated with the difference. In this case, because the payee earns 50 HKD per month:

$(50 + 60 - 100) = 10 \text{ HKD}$

Controlling Earnings Maximum or Goal Amount

You can set a goal amount for earnings—an upper limit on the earnings so that no more than that amount is paid in an accumulation period. CASHADV is set up with this control. It is set up to have a quarterly limit. You can nominate a goal amount to be paid for earnings or deductions.

CASHADV is always 20 percent of the CASHADV earning and the recovery ceases to resolve when the cash advance goal balance accumulator equals zero.

When termination occurs, the whole cash advance goal balance is recovered in the last pay period, so the deduction amount of the CASHADV is overridden by the cash advance goal balance accumulator. A negative net balance is allowed when the net amount is not enough to recover the whole goal balance.

Example

If the total accumulated deduction amount exceeds the goal amount, then only the difference is deducted. For example, suppose that a payee's deduction is 50 HKD. After the deduction, the accumulated amount is 10050 HKD and the goal amount is 10040 HKD. In this case, the system deducts only 40 HKD. The concept of the goal amount is similar to the maximum amount. The difference is that the accumulated amount is a life-to-date accumulator.

A formula determines whether the earning amount exceeds the goal amount. If it does, then the difference is returned and a warning message appears.

See Also

Chapter 6, "Defining Earnings," Calculating Cash Advances, page 59

Chapter 7, "Defining Deductions," Calculating Cash Advance Recovery, page 74

Scheduling Earnings Using Generation Control

Generation control elements enable you to instruct the system to process an earning element based on criteria that you define.

For Hong Kong, you control the payment of an earning by assigning one of three generation controls to the earning:

- OE GC GRA.
- GM GC 13MTH PAY.
- GM GC RSLV ONCE.

For each generation control, there is a corresponding formula. When the formula returns TRUE, the earnings are paid.

For example, to pay an education allowance, the generation control CM GC RSLV ONCE resolves the allowance if either of the following conditions is true:

- The allowance has not been paid this year.
- Period segmentation occurred and the allowance was paid (hence, segmentation status is inactive).

The generation control CM GC RSLV ONCE ensures that the allowance is paid only once per year if period segmentation occurs.

See Also

Chapter 6, "Defining Earnings," Calculating Gratuity Earnings, page 57

Chapter 6, "Defining Earnings," Calculating the Thirteen Month Pay, page 58

PeopleSoft Enterprise Global Payroll 9.1 PeopleBook, "Defining Calculation Elements," Defining Generation Control Elements

Chapter 7

Defining Deductions

This chapter provides overviews on deductions for Hong Kong and delivered deduction elements, and discusses how to:

- Calculate leave without pay and daily rate reduction.
- Schedule deductions using generation control.

Understanding Deductions for Hong Kong

PeopleSoft has created several deductions to demonstrate the flexibility of the Global Payroll rules to meet common processing requirements such as the preservation of minimum net pay. The following sections discuss:

- How you can use deductions and supporting elements to produce desired results.
- How PeopleSoft has met specific deduction processing requirements.

Note. User keys enable you to track an accumulator at levels lower than the employee record. This directs the system to maintain different accumulated numbers for each of the employee's locations. User Key 1 for deductions on the Deduction Accumulators page is PAY ENTITY (required by Inland Revenue reporting). User Key 2 for all year to date accumulators is CM VR BAL GRP ID (balance group ID).

See Also

[Chapter 6, "Defining Earnings," page 47](#)

Understanding Delivered Deduction Elements

This section discusses:

- Delivered deduction elements.
- Process lists and sections.
- Viewing delivered elements.
- Calculating cash advance recovery.

- Calculating community chest.
- Calculating MPF deductions.

Delivered Deduction Elements

You use these delivered deduction elements as delivered, modify them, or create new elements.

<i>Name and Description</i>	<i>Unit</i>	<i>Rate</i>	<i>Base</i>	<i>Percent</i>	<i>Amount</i>
CASHADVR Cash Advance Recovery (GC)	NA	NA	OE FM CASHADVR BSE	20 (N)	NA
COMCHST Community Chest (GC)	NA	NA	NA	NA	Payee Level
ERMPFMN1 MPF Employer Mandatory 1 (Regular)	NA	NA	MPF FM ERMN1 BASE	5 (N)	NA
ERMPFMN2 MPF Employer Mandatory 2 (Permitted Period)	NA	NA	MPF FM ERMN2 BASE	5 (N)	NA
ERMPFVOL1 MPF Employer Voluntary 1 (Regular)	NA	NA	MPF FM ERVOL1 BASE	5 (N)	NA
ERMPFVOL2 MPF Employer Voluntary 2 (Permitted Period)	NA	NA	MPF FM ERVOL2 BASE	5 (N)	NA
EEMPFMN1 MPF Employee Mandatory 1 (Regular)	NA	NA	MPF FM EEMN1 BASE	5 (N)	NA

Name and Description	Unit	Rate	Base	Percent	Amount
EEMPFMN2 MPF Employee Mandatory 2 (Permitted Period)	NA	NA	MPF FM EEMN2 BASE	5 (N)	NA
EEMPFVOL1 MPF Employer Voluntary 1 (Regular)	NA	NA	Payee Level	100 (N)	NA
EEMPFVOL2 MPF Employee Voluntary 2 (Permitted Period)	NA	NA	Payee Level	100 (N)	NA

In the following table, the first column combines the deduction name and description. The letters GC in a row indicate that the deduction has generation control. The other five columns indicate the deduction's calculation rule: Unit \times Rate, Unit \times Rate \times Percent, or Base \times Percent. The formulas used for some of the deduction codes are discussed in further detail. The letter N in a row indicates numeric.

Process Lists and Sections

The CASHADVR and COMCHST deductions are members of the DED SE COMMON process section.

The ERMPFMN1, ERMPFMN2, ERMPFVOL1, ERMPFVOL2, EEMPFMN1, EEMPFMN2, EEMPFVOL1, and EEMPFVOL2 deductions are members of the MPF SE DEDUCTION process section.

The DED SE COMMON and MPF SE DEDUCTION sections are included in the CM PR PAYROLL process list.

Viewing Delivered Elements

PeopleSoft delivers a query that you can run to view the names of all delivered elements designed for Hong Kong. Instructions for running the query are provided in the *PeopleSoft Enterprise Global Payroll 9.1 PeopleBook*.

See Also

PeopleSoft Enterprise Global Payroll 9.1 PeopleBook, "Viewing Delivered Elements," Understanding How to View Delivered Elements

Calculating Cash Advance Recovery

Employees can be paid 50 percent of their basic salary cash advances (CASHADV), which they must pay back using CASHADV in installments over five months. Use the cash advance recovery deduction exclusively to offset the cash advance. For cash advance payments, employees do not pay interest.

As the total cash advance recovery amount is deducted from the annual taxable income, the cash advance recovery is a taxable deduction.

The generation control CM GC RSLV CSHADV determines when the deduction starts and stops, if period segmentation occurs.

The formula DED FM RSLV CSHADR is attached to the generation control and determines if the cash advance accumulator is greater than zero. If so, the deduction is resolved. The accumulator is timed after calculation because the deduction is resolved after the CASHADV earning is paid (the accumulator is updated after the deduction—not when the earning is resolved). The first time that the earning is paid, the deduction is not resolved because the accumulator is updated at the end of the pay run.

In the next period, the deduction is resolved because the accumulator would have been updated with the earning amount. The generation control determines if the goal amount balance has been reached.

Example

A salaried employee's current basic salary is 20000 HKD per month. The organization decided that 50 percent of that basic salary cash advance is paid on January 15, 2001. The cash advance amount that the employee will receive on January 15, 2001 is calculated as:

$$(50 \text{ percent}) \times 20000 = 10000 \text{ (Cash Advance)} = 10000 \text{ HKD}$$

After the cash advance is finalized, the deduction cash advance recovery is created (20 percent of cash advance with goal amount for the payee on the Earnings and Deductions Assignment page).

See Also

Chapter 6, "Defining Earnings," Calculating Cash Advances, page 59

Calculating Community Chest

The community chest deduction enables employees to donate to charity from their salaries. The donated amount is a taxable deduction and is paid at the earning assignment level. Proration is not applicable to the donation.

The generation control CM GC RSLV ONCE prevents deducting the allowance more than once if period segmentation occurs.

Calculating Mandatory Provident Fund Deductions

All members of the workforce, between age 18 and 65, except those who are exempt, are required to make regular contributions to registered Mandatory Provident Fund (MPF) schemes. Contributions are calculated at 10 percent of the employee's income, with the employee and employer each paying 5 percent. Both the employee and employer can elect to make additional voluntary contributions.

The employer and employees' contributions are deducted and paid to the selected MPF scheme each pay period. After the MPF scheme receives the deductions, they are immediately deposited into the employees' retirement savings plans.

Eight MPF deductions are provided:

- Employer MPF Regular Mandatory 1 - ERMPFMN1.

The ERMPFMN1 deduction is used for employer regular MPF mandatory contributions.

- Employer MPF Permitted Period Mandatory 2 - ERMPFMN2.

The ERMPFMN2 deduction is used for employer MPF mandatory contributions during the 60-day permitted period.

- Employer MPF Regular Voluntary 1- ERMPFVOL1.

The ERMPFVOL1 deduction is an additional 5 percent of relevant earnings and should be given to all employees. The rest of the rules are the same as for the MPF Employer Voluntary deduction. The deduction is used for employer MPF voluntary contributions.

- Employer MPF Permitted Period Voluntary 2 - ERMPFVOL2.

The ERMPFVOL2 deduction is used for employer MPF voluntary contributions during the 60-day permitted period.

- Employee MPF Regular Mandatory 1 - EEMPFMN1.

The EEMPFMN1 deduction is used for employee MPF mandatory contributions.

- Employee MPF Permitted Period Mandatory 2 - EEMPFMN2.

The EEMPFMN2 deduction is used for employee MPF mandatory contributions during the 60-day permitted period.

- Employee MPF Regular Voluntary 1 - EEMPFVOL1.

The EEMPFVOL1 deduction is used for employer MPF voluntary contributions.

- Employee MPF Permitted Period Voluntary 2 - EEMPFVOL2.

The EEMPFVOL2 deduction is used for employee MPF voluntary contributions during the 60-day permitted period.

See Also

Chapter 8, "Administering Mandatory Provident Fund Contributions," page 77

Calculating Leave Without Pay and Daily Rate Deduction

Employees might take leave without pay during their working periods. One calendar daily rate is taken from salary for one day of unpaid leave. Unpaid leave is a taxable deduction.

LWOP can be taken anytime during the servicing period. One DAILY RT is reduced from the employee's monthly income for every single day of LWOP taken. The value of one DAILY RT equals:

$(\text{Annual Salary}) / 365$

365 is used even in the leap year.

Example

Three days of unpaid leave has been taken in April and the basic salary in April is 10000 HKD. The April monthly salary is calculated as:

Basic Salary:	10000
Unpaid Leave:	- 3 (3/30) x 10000
Net:	(HKD) 9000

April Monthly Salary Calculation

A salary change can occur during unpaid leave. In this case, the unpaid leave is split into two segments: segment one is based on the old daily rate and segment two is based on the new daily rate.

See Also

[Chapter 6, "Defining Earnings," Calculating Leave Without Pay \(LWOP\), page 61](#)

[Chapter 6, "Defining Earnings," Calculating Leave Without Pay \(LWOP2\), page 62](#)

Scheduling Deductions Using Generation Control

Generation control elements enable you to specify whether to process a deduction element based on defined criteria. For Global Payroll for Hong Kong, the system controls deduction payments by assigning a generation control to the deductions.

For each generation control, there is a corresponding formula. When the formula returns TRUE, the deduction is resolved.

See Also

PeopleSoft Enterprise Global Payroll 9.1 PeopleBook, "Defining Calculation Elements," Defining Generation Control Elements

Chapter 8

Administering Mandatory Provident Fund Contributions

This chapter provides overviews of the administration of Mandatory Provident Fund (MPF) contributions and MPF proration rules, and discusses how to:

- Make statutory and customary MPF deductions.
- Accommodate MPF exemption rules and limits.
- Calculate permitted period MPF contributions.
- Calculate regular MPF contributions.
- Set up additional MPF recipient details.
- Submit the Remittance Statement.

Understanding the Administration of Mandatory Provident Fund Contributions

This section discusses the administrative and reporting requirements of MPF administration and maintenance to:


- Support both employee and employer payments to a nominated fund in accordance with the calculation of eligibility rules for MPF legislation.

These deduction rules cover legislative MPF requirements such as permitted period processing, age eligibility, and the contribution holiday rule.

- Provide reports to support MPF administrative requirements.

MPF reports such as the Remittance Statement and Terminated Employees Report enable you to manage MPF contributions.

The following diagram displays the rules and options that you are required to set up or exercise to ensure correct MPF calculation and system outputs:



User inputs and system outputs for Mandatory Provident Fund deductions

See Also

[Appendix A, "Appendix: Global Payroll for Hong Kong Reports," page 157](#)

[Chapter 6, "Defining Earnings," Calculating Mandatory Provident Fund Earnings, page 64](#)

[Chapter 7, "Defining Deductions," Calculating Mandatory Provident Fund Deductions, page 75](#)

Common Elements Used in This Chapter

Casual Employee (as defined by MPF Ordinance)

An employee engaged in the construction or catering industry, who is employed on a daily basis or for a fixed period of less than sixty days.

Contribution Day	<p>For non-casual employees, the tenth day after the last day of the contribution period or the contribution period in which the permitted period ends—whichever is later. The employer must contribute to a scheme for their employees on or before the tenth day after the last day of the contribution period.</p> <p>For casual employees (who are not members of an industry scheme), this is the tenth day after the last day of the relevant contribution period, or the contribution period in which the permitted period ends—whichever is later. The employer and the approved trustee of the scheme concerned approve one of the following days:</p> <ul style="list-style-type: none"> • The day on which the casual employee is paid. • The tenth day after the last day of the relevant contribution period.
Contribution Holiday	An employee does not have to contribute to MPF for the first thirty days of employment. The first thirty days is referred to as the contribution holiday. An employee must start paying MPF from the thirty-first day of employment.
Contribution Period (non-casual employee)	Regarded as the payroll period. If an employee is paid on a calendar month basis and the payment pattern is specified in the employment contract, the contribution period should be one calendar month.
Employee Reporting Period	The pay period in which the holiday contribution period ends. Employee's can start contributing to MPF in this period.
Employer Reporting Period	The pay period subsequent to the period in which the contribution holiday ends. The remittance report and payslip are required to disclose the contribution amount and contribution dates within the permitted period.
Mandatory Provident Fund (MPF)	A compulsory retirement plan scheme for employees between the ages of 18 and 65, implemented by the government of Hong Kong to help ensure a financially sound retirement for the territory's workforce. Under MPF, both the employer and employee make regular mandatory contributions into an employee's account, with benefits payable at retirement.
Permitted Period	For casual employees, the period within which the employer must enroll the employee into a registered scheme—ten days for casual employees.
Permitted Period MPF Deduction	An MPF deduction (contribution amount) for the permitted period required for the MPF Remittance report. Used to report MPF contribution within the permitted period and does not contribute to balance accumulators.
Regular MPF Deduction	Regular MPF deductions are used for regular deduction processing in payroll and contribute to balance accumulators. There are two deduction elements. One element resolves the amount for payroll and the other resolves for reporting.

Viewing Delivered Elements

The PeopleSoft system delivers a query that you can run to view the names of all delivered elements designed for Hong Kong. Instructions for running the query are provided in the *PeopleSoft Enterprise Global Payroll 9.1 PeopleBook*.

See Also

PeopleSoft Enterprise Global Payroll 9.1 PeopleBook, "Viewing Delivered Elements," Understanding How to View Delivered Elements

Understanding MPF Proration Rules

Proration of relevant income only occurs for a new hire or rehire for employer contributions and when an employee turns 18 years of age within the period.

This section discusses:

- The MPF PO REVLNT INCM proration rule.
- The MPF PO 18TH BTHDAY proration rule.
- The MPF PO 65TH BTHDAY proration rule.

See Also

Appendix A, "Appendix: Global Payroll for Hong Kong Reports," page 157

Chapter 6, "Defining Earnings," Calculating Mandatory Provident Fund Earnings, page 64

Chapter 7, "Defining Deductions," Calculating Mandatory Provident Fund Deductions, page 75

Chapter 8, "Administering Mandatory Provident Fund Contributions," Accommodating MPF Exemption Rules and Limits, page 84

Chapter 8, "Administering Mandatory Provident Fund Contributions," Calculating Permitted Period MPF Contributions, page 91

Chapter 8, "Administering Mandatory Provident Fund Contributions," Calculating Regular MPF Contributions, page 93

PeopleSoft Enterprise Global Payroll 9.1 PeopleBook, "Defining Calculation Elements," Defining Proration Rules

The MPF PO REVLNT INCM Proration Rule

The MPF PO REVLNT INCM proration rule is used to prorate relevant income for new hire/rehires. The proration rule calculation is:

Days of service since period hire date or rehire date / number of days in a period.

The MPF FM POST EEVOL1 formula prorates the employee voluntary contribution amount if the employee is a new hire.

The MPF PO 18TH BTHDAY Proration Rule

If the employee's eighteenth birthday falls within the contribution period in which the thirty first day of employment falls, prorating of the minimum and maximum levels of relevant income for the employee's first mandatory contribution is required. The MPF PO 18TH BTHDAY proration rule prorates relevant income when the employee turns 18 years of age. The proration rule calculation is defined as follows:

Number of days contributed in a month / number of days in month.

If a period spans two months, for example October 15, 2007 – November 1, 2007, the relevant income is 10000 HKD and the employee's birthday falls on the 16th, then contribution is prorated as follows:

$$(16/31 \times 10000 \times 5\%) + (14/30 \times 10000 \times 5\%) = 508.06.$$

For example, suppose an employee is hired on February 1 and turns 18 on May 16, 2007, then the employee's relevant income for May 2007 is 10000 HKD. MPF for May is calculated as follows:

31st day of employment: March 3, 2007

18th birthday: May 16, 2007

Relevant income (May 16 - 31, 2007): 10000 HKD X 16/31 = 5161.29 HKD

Max relevant income level: 20000 HKD

Min relevant income level: 4000 HKD

Employee's mandatory contribution for May 2007: 5161.29 HKD X 5%

Employer's mandatory contribution for May 2007: 5161.29 HKD X 5%

MPF PO 65TH BTHDAY Proration Rule

Effective October 1 2004, the MPF guidelines were revised by the Hong Kong Government. The revised guidelines stipulate the new calculation of mandatory contributions for employees who attain the age of 65 on or after 1 October 2004. Mandatory contributions are required based on the relevant income earned by the employees up to the day before their 65th birthday regardless of when the income was actually paid to them.

If the employee's 65th birthday falls within the pay period, prorating of the minimum and maximum levels of relevant income for the employee's last mandatory contribution is required. The MPF PO 65TH BTHDAY proration rule prorates relevant income when the employee turns 65 years of age. The proration rule calculation is defined as follows:

Number of days contributed in a month / number of days in month.

Example 1: Relevant income earned up to the day before the 65th birthday is between the minimum and maximum levels of \$5,000 and \$20,000 per month:

Date of 65th birthday: 18 October 2004

Contribution period start date : 1 October 2004

Contribution period end date: 31 October 2004

Relevant income: \$12,000 (for October 2004)

Amount of employer contribution: \$329.13 ($\$12,000 \times 17/31 \times 5\%$)

Amount of employee contribution: \$329.13 ($\$12,000 \times 17/31 \times 5\%$)

Example 2: Relevant income earned up to the day before the 65th birthday is above the maximum level of \$20,000 per month:

Date of 65th birthday: 18 October 2004

Contribution period start date: 1 October 2004

Contribution period end date: 31 October 2004

Relevant income: \$38,000 (for October 2004)

Amount of employer contribution: \$1,000.00 ($\$20,000 \times 5\%$)

Amount of employee contribution: \$1,000.00 ($\$20,000 \times 5\%$)

Making Statutory and Customary MPF Deductions

This section discusses the MPF deductions that are delivered by PeopleSoft.

PeopleSoft supplies the following deductions for the common MPF contributions. The deductions are PeopleSoft maintained and are all defined with a calculation rule of Base x Percent. Mandatory and voluntary deductions are delivered for both employers and employees.

<i>Deduction</i>	<i>Description</i>
ERMPFMN1 Employer Regular MPF Mandatory Contribution	Used for employer regular MPF mandatory contributions. Base = MPF FM ERMN1 Percent = 5 (Statutory)
ERMPFMN2 Employer Permitted Period MPF Mandatory Contribution	Used for employer MPF mandatory contributions within the sixty-day permitted period. Base = MPF FM ERMN2 Percent = 5 (Statutory)
ERMPFVOL1 Employer Regular MPF Voluntary Contribution	An additional 5 percent of relevant earnings and should be given to all employees. The rest of the rules are the same as those for the MPF Employer Voluntary deduction. The deduction is used for employer MPF voluntary contribution. Base = MPF FM ERVOL1 BASE Percent = 5 (Customary)

<i>Deduction</i>	<i>Description</i>
ERMFPVOL2 Employer MPF Permitted Period Voluntary Contribution	Used for employer MPF voluntary contributions within the sixty-day permitted period. Base = MPF FM ERVOL2 BASE Percent = 5 (Customary)
EEMPFMN1 Employee Regular Mandatory MPF Contribution	Used for employee MPF mandatory contributions. Base = MPF FM EEMN1 BASE Percent = 5 (Statutory)
EEMPFMN2 Employee Permitted Period Mandatory MPF Contribution	Used for employee MPF mandatory contributions within the sixty-day permitted period. Base = MPF FM EEMN2 BASE Percent = 5 (Statutory)
EEMPVOL1 Employee Regular Voluntary MPF Contribution	Used for employee MPF voluntary contributions. Entered at the deduction assignment level. Base = Payee Level Percent = 100 (Customary)
EEMPVOL2 Employee Permitted Period Voluntary contribution	Used for employee MPF voluntary contributions within the sixty-day permitted period. Entered at the deduction assignment level. Base = Payee Level Percent = 100 (Customary)

Note. Earnings that are included in the MPF calculation are referred to as relevant income and include wages, salaries, leave pay, fee, commission, bonus, and gratuity. Because not all earnings are included in MPF calculations, it is possible to define the earnings that should be included in MPF calculation using the earning component.

See Also

Appendix A, "Appendix: Global Payroll for Hong Kong Reports," page 157

Chapter 6, "Defining Earnings," Calculating Mandatory Provident Fund Earnings, page 64

Chapter 7, "Defining Deductions," Calculating Mandatory Provident Fund Deductions, page 75

Chapter 8, "Administering Mandatory Provident Fund Contributions," Calculating Permitted Period MPF Contributions, page 91

Chapter 8, "Administering Mandatory Provident Fund Contributions," Calculating Regular MPF Contributions, page 93

Accommodating MPF Exemption Rules and Limits

This section provides overviews of accommodating MPF exemption rules and limits, the MPF contribution holiday rule, age eligibility rules, and permitted period termination rules, and discusses how to:

- Define casual employees for MPF contributions.
- Exclude employees from MPF calculations.
- Apply maximum and minimum limits to MPF contributions.

Understanding Accommodating MPF Exemption Rules and Limits

This section discusses the exceptions and limits for MPF contributions.

Although it is mandatory for employers to pay MPF contributions for each employee, the following exemptions and limits exist:

- An employee does not have to contribute to MPF for the first thirty days (contribution holiday) of employment.
- If the employee is paid on a monthly calendar basis, reaches the age of 65 prior to the period begin date, and is not terminated, then MPF contribution is not required by either the employer or the employee for that month.
- If an employee terminates within the first sixty days of employment (permitted period), the employer is exempted from making the MPF contribution.
- For casual employees, the sixty-day (permitted period) rule for employers and thirty-day (contribution holiday) rule for employees does not apply.
- Mandatory contributions are subject to maximum and minimum levels.

For example, employees earning less than 5000 HKD per month in relevant income do not have to contribute to MPF, but the employer still needs to contribute 5 percent of the employee's income, even if the employee earns less than 5000 HKD in relevant income in the month. Employer mandatory contributions have no minimum levels.

Note. No age eligibility or minimum and maximum rules are applied to employee voluntary deductions. However, employer voluntary deductions do check for these rules.

Understanding the MPF Contribution Holiday Rule

This section discusses generation control resolution and the MPF deduction.

A generation control resolves the MPF deduction if the employee's service days are greater than thirty days. For example, for the EEMPFMN1 deduction, the MPF generation control MPF GC EEMN1, using formula MPF FM RSLV EEMN1, resolves if the employee's service days are greater than thirty days (not within the holiday contribution period) and no additional exemptions apply.

Depending on whether the employee is hired or rehired, days of service are calculated as:

Period End Date – Hire Date + 1

or

Period End Date – Rehire Date + 1

If the contribution holiday end date MPF DT HOL END DT is before or the same as the PERIOD END DATE, then the formula MPF FM HOL END DT resolves. The formula determines if the period is greater than the contribution holiday end date.

The formula MPF FM END HOL PRD compares the holiday contribution end date to the pay period begin date. The rule states that if the holiday end date does not fall on the first day of a pay period then the employee's MPF contribution will be waived until the next full pay period. Contributions begin when the pay period begin date is greater than the contribution holiday end date. For example, suppose a monthly paid employee is hired on February 1, 2007, and the holiday end period is April 3, 2007. Because the April pay period starts on the 1st, the employee will not have to contribute MPF until the next pay period (May 1, 2007).

See Also

[Appendix A, "Appendix: Global Payroll for Hong Kong Reports," page 157](#)

[Chapter 6, "Defining Earnings," Calculating Mandatory Provident Fund Earnings, page 64](#)

[Chapter 7, "Defining Deductions," Calculating Mandatory Provident Fund Deductions, page 75](#)

[Chapter 8, "Administering Mandatory Provident Fund Contributions," Calculating Permitted Period MPF Contributions, page 91](#)

[Chapter 8, "Administering Mandatory Provident Fund Contributions," Calculating Regular MPF Contributions, page 93](#)

Understanding MPF Age Eligibility Rules

This section discusses the formulae used to check the employees age before resolving and determining the payment of MPF contributions.

The formula MPF FM AGE 65 checks if the employee is 65 years of age. The formula calls GP AGE IN YEARS to calculate the employee's age and resolves when the following conditions are true:


- The employee's age is 65.
- The employee's birthday falls within the period and on or before the payment date. The formula MPF FM 65 BIRTHDAY is used to check if the employee's 65th birthday falls within the pay period.

Note. GP AGE IN YEARS calculates the number of years from the employee's birthdate to the period end date.

The generation controls MPF GC ERMN1 and MPF GC ERMN2 stop resolving MPF mandatory deductions once the employee has reached 65 before the period begin date. The following example illustrates how the payment date determines the payment of MPF contributions.

Employees Turning 65 Before The Period End Date

Suppose an employee turns 65 before the period end date. In Period 1, MPF is resolved; in Period 2, MPF is also resolved because the employee turns 65 before the period end date, however, the MPF values are prorated up to the day before the employee's 65th birthday. In Period 3, since the employee is already 65, MPF isn't resolved. The following diagram illustrates this scenario:



An employee turns 65 before the period end date

Note. If the employee ceases employment immediately upon reaching the age of 65 and all outstanding relevant income is paid or payable on the day before the employee's 65th birthday, the final payment is considered a relevant income and contributions are payable on it.

See Also

[Appendix A, "Appendix: Global Payroll for Hong Kong Reports," page 157](#)

[Chapter 6, "Defining Earnings," Calculating Mandatory Provident Fund Earnings, page 64](#)

[Chapter 7, "Defining Deductions," Calculating Mandatory Provident Fund Deductions, page 75](#)

[Chapter 8, "Administering Mandatory Provident Fund Contributions," Calculating Permitted Period MPF Contributions, page 91](#)

[Chapter 8, "Administering Mandatory Provident Fund Contributions," Calculating Regular MPF Contributions, page 93](#)

Understanding MPF Permitted Period Termination Rules

This section discusses MPF and termination rules.

Termination is only considered if the employee terminates from a primary job. The array MPF AR PRIM JOB retrieves the hire date, rehire date, and termination date from the job table for the employee's primary job. The formula MPF FM TERM CONTRB checks if the employee terminates before the employee's birthday, using the following elements:

- MPF FM TERMINATE - Determines if the termination is within the permitted period.
- MPF VR TERM DATE - Resolves the termination date.
- MPF DT BIRTHDAY - Resolves the birth date.

The formula MPF FM TERM CONTRB resolves if the termination date is before the employee's birthday. If the employee turns 65 within the contribution period and terminates before age 65, then the MPF contribution is deducted.

Note. If an employer decides to make the first contribution during the first sixty days of employment (permitted period), MPF is calculated and deducted for the employee.

Working with Contributions on the Last Day of Employment

The contribution period for a terminated employee can also end on the date the employee is terminated. If the employee's contract states that the final contribution should be paid on the last date of employment, then the mandatory contributions for the relevant employee should be paid to the trustee on or before the tenth day after the date of cessation of employment.

For example, suppose a relevant employee paid on a calendar month basis ceases employment on April 10, 2007 and all outstanding relevant income is paid on that day, the mandatory contributions for the last contribution period should fall due on April 20, 2007. However, if their salary for April is payable under the employment contract on April 30 (following the normal pay cycle) the contribution period would end on April 30, and the mandatory contributions would be due on May 10.

Note. In the period the employee terminates, the maximum and minimum limits are not prorated.

See Also

[Appendix A, "Appendix: Global Payroll for Hong Kong Reports," page 157](#)

[Chapter 6, "Defining Earnings," Calculating Mandatory Provident Fund Earnings, page 64](#)

[Chapter 7, "Defining Deductions," Calculating Mandatory Provident Fund Deductions, page 75](#)

[Chapter 8, "Administering Mandatory Provident Fund Contributions," Calculating Permitted Period MPF Contributions, page 91](#)

[Chapter 8, "Administering Mandatory Provident Fund Contributions," Calculating Regular MPF Contributions, page 93](#)

[Chapter 13, "Defining Absence Rules," Calculating Absence Entitlements on Termination, page 147](#)

Defining Casual Employees for MPF Contributions

Contributions for casual employees are calculated each pay or contribution period. Casual employees are processed in a separate pay group from other employees as they are most often paid daily.

As there is a difference between the way that casual employees and non-casual employees are calculated, you can mark an employee as a casual employee. The variable MPF VR CASUAL FLG (casual pay group staff flag) is delivered as customary data and is attached at the pay group override level to indicate whether the pay group is for casual employees.

See Also

Appendix A, "Appendix: Global Payroll for Hong Kong Reports," page 157

Chapter 6, "Defining Earnings," Calculating Mandatory Provident Fund Earnings, page 64

Chapter 7, "Defining Deductions," Calculating Mandatory Provident Fund Deductions, page 75

Chapter 8, "Administering Mandatory Provident Fund Contributions," Calculating Permitted Period MPF Contributions, page 91

Chapter 8, "Administering Mandatory Provident Fund Contributions," Calculating Regular MPF Contributions, page 93

Excluding Employees from MPF Calculations

This section discusses how to exclude specific employees from MPF calculations.

Although all members of the workforce between the ages of 18 and 65 are eligible for MPF, you may have to exclude an employee from MPF calculations. The CM SE INITIALISE section (common initialize section paid by eligibility) is delivered as an example. You can change the section to pay by payee and exclude specific employees from MPF calculations by entering the deduction as inapplicable at the deduction assignment level. By doing this, the employee is exempted from MPF calculations in every pay run.

See Also

Chapter 8, "Administering Mandatory Provident Fund Contributions," Accommodating MPF Exemption Rules and Limits, page 84

Appendix A, "Appendix: Global Payroll for Hong Kong Reports," page 157

Chapter 6, "Defining Earnings," Calculating Mandatory Provident Fund Earnings, page 64

Chapter 7, "Defining Deductions," Calculating Mandatory Provident Fund Deductions, page 75

Chapter 8, "Administering Mandatory Provident Fund Contributions," Calculating Permitted Period MPF Contributions, page 91

Chapter 8, "Administering Mandatory Provident Fund Contributions," Calculating Regular MPF Contributions, page 93

Applying Maximum and Minimum Limits to MPF Contributions

Mandatory contributions are subject to maximum and minimum levels. For example, employees earning less than 5000 HKD per month in relevant income do not have to contribute to MPF. However, the employer still needs to contribute 5 percent of the employee's income, even if the employee earns less than 5000 HKD in relevant income in the month. Employer mandatory contributions have no minimum levels. For employees earning more than 20000 HKD per month, mandatory contributions for employer and employee are capped at 1000 HKD (5 percent of 20000 HKD).

Note. MPF calculations for pay periods other than monthly are identical, except that the maximum and minimum levels of relevant income will vary.

The MPF BR MINMAX REVL bracket stores the minimum (variable MPF VR MIN LEVEL) and maximum (variable MPF VR MAX LEVEL) relevant income ceiling for each period frequency. The following table lists the maximum and minimum levels of contribution for the different pay periods:

<i>Pay Period</i>	<i>Min Level of Relevant Income</i>	<i>Max Level of Relevant Income</i>
Daily	160	650
Weekly	1120	4550
Biweekly	2240	9100
Fortnightly	2240	9100
Monthly	5000	20000
Quarterly	8000	40000
Yearly	48000	240000

This rule enables you to run multiple calendars in a period. For example, you can run a regular pay run and thirteenth month pay in separate calendars. The rules calculate contributions as follows:

Regular Run

Relevant Income = 19000

MPF contribution = 19000 x 5%

Thirteenth Month

Relevant Income = 19000

MPF Contribution = 1000 x 5%

MPF contribution is calculated on 1000 HKD instead of 19000 HKD in the thirteenth month pay run because MPF is capped at 20000 HKD.

Note. If an employee has concurrent jobs, the maximum and minimum limits are applied per employee, not per job. The holiday period is applied to the earliest hire date (or rehire date) of the employee's primary job regardless of whether the employee has concurrent jobs.

Commencing Employee MPF Contributions

Contributions for the period in which the employee's contribution holiday ends are calculated on a prorated basis. Prorating may be performed based on the number of days in the month. On this basis, the minimum levels of relevant income for one day in October (a 31 day month) and one day in November (a 30 day month) would be 129 HKD and 133 HKD respectively. Accordingly, the minimum levels of relevant income for the week from October 29, 2007 to November 4, 2007 would be:

919 HKD (3 x 129 + 4 x 133)

Note. You can use 160 HKD and 650 HKD as the daily minimum and maximum levels of relevant income. The minimum and maximum levels for contribution periods longer than a day are calculated as a multiple of the daily minimum and maximum levels.

For example, suppose an employee is paid monthly and commences employment on April 11 and his or her monthly salary is 18000 HKD, and the employee's contribution holiday ends on May 10. For the purposes of calculating their mandatory contributions for the month ending May 31:

The employee's relevant income = 12194 HKD (being 18000 HKD x 21/31)

The maximum relevant income level = 13545 HKD (being 20000 HKD / 31 rounded to closest dollar x 21)

The minimum relevant income level = 2709 HKD (being 4000 HKD / 31 rounded to closest dollar x 21)

Since the relevant income is between 2709 HKD and 13545 HKD, the mandatory contributions for the month ending May 31 = 609.28 HKD (being 12194 HKD x 5%).

See Also

Appendix A, "Appendix: Global Payroll for Hong Kong Reports," page 157

Chapter 6, "Defining Earnings," Calculating Mandatory Provident Fund Earnings, page 64

Chapter 7, "Defining Deductions," Calculating Mandatory Provident Fund Deductions, page 75

Chapter 8, "Administering Mandatory Provident Fund Contributions," Calculating Permitted Period MPF Contributions, page 91

Chapter 8, "Administering Mandatory Provident Fund Contributions," Calculating Regular MPF Contributions, page 93

Calculating Permitted Period MPF Contributions

This section provides an overview of permitted period MPF contributions and discusses how to:

- Calculate employer mandatory permitted period MPF contributions.
- Calculate employee mandatory permitted period MPF contributions.
- Calculate employer and employee voluntary permitted period MPF contributions.

Understanding Permitted Period MPF Contributions

Permitted MPF deductions only resolve during the sixty-day employment period (permitted period). One MPF deduction is resolved in every period for reporting, so the reports can retrieve the contribution periods in which the permitted MPF deduction is resolved.

The formula MPF FM PERM PERIOD checks whether the current period falls within the permitted period and resolves whether the period begin date is less than or equal to the permitted period end date.

The date MPF DT PERM END DT returns the permitted period end date. Depending on whether the employee is hired or rehired, the permitted period end date calculation is as follows:

Hire date + 59 days

or

Rehire date + 59 days

Note. It is possible that you will make MPF contributions immediately and not wait until the permission period has elapsed. Since rules cater for the permission period, you are required to remove all associated PeopleSoft rules that cater for the permission period; hence, these deductions are processed as regular deductions.

See Also

[Appendix A, "Appendix: Global Payroll for Hong Kong Reports," page 157](#)

[Chapter 6, "Defining Earnings," Calculating Mandatory Provident Fund Earnings, page 64](#)

[Chapter 7, "Defining Deductions," Calculating Mandatory Provident Fund Deductions, page 75](#)

[Chapter 8, "Administering Mandatory Provident Fund Contributions," Calculating Regular MPF Contributions, page 93](#)

[Chapter 8, "Administering Mandatory Provident Fund Contributions," Accommodating MPF Exemption Rules and Limits, page 84](#)

Calculating Employer Mandatory Permitted Period MPF Contributions

The ERMPFMN2 contribution is calculated at 5 percent of relevant income for employees between the ages of 18 and 65 if they have relevant income greater than 4000 HKD for the month. The maximum relevant income that is included in the calculation is 20000 HKD.

The formula MPF FM ERMN2 with generation control MPF GC ERMN2 (using formula MPF FM ERMN2) resolves if the following conditions are true:

- The employee's age is greater than or equal to 18 and less than 65, or
- The employee's age is 65 and their birthday falls within the period, and
- The period is within the permitted period.

The generation control stops resolving the deductions once the employee's age is above 65 before the period begin date.

The bracket MPF BR MINMAX REVL retrieves the minimum and maximum amount associated with the period frequency.

See Also

Appendix A, "Appendix: Global Payroll for Hong Kong Reports," page 157

Chapter 6, "Defining Earnings," Calculating Mandatory Provident Fund Earnings, page 64

Chapter 7, "Defining Deductions," Calculating Mandatory Provident Fund Deductions, page 75

Chapter 8, "Administering Mandatory Provident Fund Contributions," Calculating Regular MPF Contributions, page 93

Chapter 8, "Administering Mandatory Provident Fund Contributions," Accommodating MPF Exemption Rules and Limits, page 84

Calculating Employee Mandatory Permitted Period MPF Contributions

The formula MPF FM EEMN2 BASE with generation control MPF GC EEMN2 (using formula MPF FM RSLV EEMN2) calculates the relevant income for employee mandatory contributions within the permitted period, based on the following:

- Relevant income is prorated if the employee is a new hire or rehire (using the formulas MPF FM SET STARTDT, MPF FM PERM STRTDT, and MPF FM SET EE STRT).
- Relevant income is prorated if the employee turns 18 years of age (using formula MPF FM AGE 18-64 and prorate using MPF PO 18TH BTHDAY).
- Relevant income is prorated if the employee turns 65 years of age during the pay period (using formula MPF FM 65 BIRTHDAY and prorate using MPF PO 65TH BTHDAY).

The bracket MPF BR MINMAX REVL retrieves the minimum and maximum amount associated with the period frequency.

See Also

[Appendix A, "Appendix: Global Payroll for Hong Kong Reports," page 157](#)

[Chapter 6, "Defining Earnings," Calculating Mandatory Provident Fund Earnings, page 64](#)

[Chapter 7, "Defining Deductions," Calculating Mandatory Provident Fund Deductions, page 75](#)

[Chapter 8, "Administering Mandatory Provident Fund Contributions," Calculating Regular MPF Contributions, page 93](#)

[Chapter 8, "Administering Mandatory Provident Fund Contributions," Accommodating MPF Exemption Rules and Limits, page 84](#)

Calculating Employer and Employee Voluntary Permitted Period MPF Contributions

The formula MPF FM ERVOL2 BASE with generation control MPF GC ERVOL2 (MPF GC EEVOL2 for employees) using formula MPF FM RSLV ERVOL2 (MPF FM RSLV EEVOL2 for employees) resolves when the period is within the permitted period.

The post processing formula MPF FM POST EEVOL2 prorates the amount.

The formula MPF FM MAX LVL using variable MPF VR MAX LEVEL determines the maximum contribution level.

See Also

[Appendix A, "Appendix: Global Payroll for Hong Kong Reports," page 157](#)

[Chapter 6, "Defining Earnings," Calculating Mandatory Provident Fund Earnings, page 64](#)

[Chapter 7, "Defining Deductions," Calculating Mandatory Provident Fund Deductions, page 75](#)

[Chapter 8, "Administering Mandatory Provident Fund Contributions," Calculating Regular MPF Contributions, page 93](#)

[Chapter 8, "Administering Mandatory Provident Fund Contributions," Accommodating MPF Exemption Rules and Limits, page 84](#)

Calculating Regular MPF Contributions

This section discusses how to:

- Calculate employers regular mandatory MPF contributions.
- Calculate employees regular mandatory MPF contributions.
- Calculate employer regular voluntary MPF contributions.

- Calculate employees regular voluntary MPF contributions.

See Also

[Appendix A, "Appendix: Global Payroll for Hong Kong Reports," page 157](#)

[Chapter 6, "Defining Earnings," Calculating Mandatory Provident Fund Earnings, page 64](#)

[Chapter 7, "Defining Deductions," Calculating Mandatory Provident Fund Deductions, page 75](#)

[Chapter 8, "Administering Mandatory Provident Fund Contributions," Accommodating MPF Exemption Rules and Limits, page 84](#)

[Chapter 8, "Administering Mandatory Provident Fund Contributions," Calculating Permitted Period MPF Contributions, page 91](#)

Calculating Employers Regular Mandatory MPF Contributions

The ERMPFMN1 contribution is calculated at 5 percent of relevant income (5 percent of earnings that are included in the MPF calculation). MPF need only be calculated for employees between 18 and 65 years of age and only on the first 20000 HKD of relevant income for the month. For casual employees, contributions are calculated and paid from day one.

While contributions have to be calculated from the employees hire date, the first contribution to MPF for non-casual employees does not have to be made on or before the first contribution day after the sixty-day employment period ends.

The post processing formula MPF FM POST ERMN1 checks if it is the reporting period. If it is, the MPF contributions from the permitted period (sixty-day employment period) and the current period are totaled.

The formula MPF FM ERMN1 with generation control MPF GC ERMN1, using formula MPF FM RSLV ERMN1, resolves when the employee is between 18 and 65 (using formula MPF FM AGE 18-64), and the contribution is calculated on the first 20000 HKD of relevant income for the month.

Contributions for casual employees with the MPF VR CASUAL FLG are calculated and paid from day one.

See Also

[Appendix A, "Appendix: Global Payroll for Hong Kong Reports," page 157](#)

[Chapter 6, "Defining Earnings," Calculating Mandatory Provident Fund Earnings, page 64](#)

[Chapter 7, "Defining Deductions," Calculating Mandatory Provident Fund Deductions, page 75](#)

[Chapter 8, "Administering Mandatory Provident Fund Contributions," Accommodating MPF Exemption Rules and Limits, page 84](#)

[Chapter 8, "Administering Mandatory Provident Fund Contributions," Calculating Permitted Period MPF Contributions, page 91](#)

Calculating Employees Regular Mandatory MPF Contributions

The formula MPF FM EEMN1 BASE with generation control MPF GC EEMN1, using formula MPF FM RSLV EEMN1, resolves the deduction if the employee's service days are greater than thirty days (not within the holiday contribution period).

The MPF FM EEMN1 formula calculates the relevant income for regular employee mandatory contributions based on the following:

- Relevant income is prorated if the employee is a new hire or rehire. (Using MPF PO REVLNT INCM).
- Relevant income is prorated if the employee turns 18 years of age. (Using MPF PO 18TH BTHDAY).
- Relevant income is prorated if the employee turns 65 years of age. (Using MPF PO 65TH BTHDAY).

The bracket MPF BR MINMAX REVL retrieves the minimum and maximum amount associated with the period frequency.

See Also

[Appendix A, "Appendix: Global Payroll for Hong Kong Reports," page 157](#)

[Chapter 6, "Defining Earnings," Calculating Mandatory Provident Fund Earnings, page 64](#)

[Chapter 7, "Defining Deductions," Calculating Mandatory Provident Fund Deductions, page 75](#)

[Chapter 8, "Administering Mandatory Provident Fund Contributions," Accommodating MPF Exemption Rules and Limits, page 84](#)

[Chapter 8, "Administering Mandatory Provident Fund Contributions," Calculating Permitted Period MPF Contributions, page 91](#)

Calculating Employer Regular Voluntary MPF Contributions

The formula MPF FM ERVOL1 BASE with generation control MPF GC ERVOL1, using formula MPF FM RSLV ERVOL1, resolves based on the following:

- Relevant income is prorated if the employee turns 18 years of age— (Using MPF PO 18TH BTHDAY).
- If the employee is not 18 years of age, the bracket MPF BR MINMAX REVL retrieves the minimum and maximum amount associated with the period frequency.

The post processing formula MPF FM POST ERVOL1 checks if it is the reporting period. If so, the MPF contribution from the permitted period and the current period are totaled.

See Also

[Appendix A, "Appendix: Global Payroll for Hong Kong Reports," page 157](#)

[Chapter 6, "Defining Earnings," Calculating Mandatory Provident Fund Earnings, page 64](#)

[Chapter 7, "Defining Deductions," Calculating Mandatory Provident Fund Deductions, page 75](#)

[Chapter 8, "Administering Mandatory Provident Fund Contributions," Accommodating MPF Exemption Rules and Limits, page 84](#)

[Chapter 8, "Administering Mandatory Provident Fund Contributions," Calculating Permitted Period MPF Contributions, page 91](#)

Calculating Employees Regular Voluntary MPF Contributions

The generation control MPF GC EEVOL1, using formula MPF FM RSLV EEVOL1, calculates the relevant income for regular employer mandatory contributions based on the following:

- Relevant income is prorated if the employee turns 18 years of age. (Using MPF PO 18TH BTHDAY).
- If the employee is not 18 years of age, then the bracket MPF BR MINMAX REVL retrieves the maximum amount associated with the period frequency.

The formula MPF FM POST EEVOL1 prorates the deduction amount.

See Also

[Appendix A, "Appendix: Global Payroll for Hong Kong Reports," page 157](#)

[Chapter 6, "Defining Earnings," Calculating Mandatory Provident Fund Earnings, page 64](#)

[Chapter 7, "Defining Deductions," Calculating Mandatory Provident Fund Deductions, page 75](#)

[Chapter 8, "Administering Mandatory Provident Fund Contributions," Accommodating MPF Exemption Rules and Limits, page 84](#)

[Chapter 8, "Administering Mandatory Provident Fund Contributions," Calculating Permitted Period MPF Contributions, page 91](#)

PeopleSoft Enterprise Global Payroll 9.1 PeopleBook, "Setting Up Accumulators"

Setting up Additional MPF Recipient Details

The administrative body to which MPF deductions are paid is treated in the system the same way as any other deduction recipient although for reporting purposes some additional MPF-specific detail is stored at recipient level.

See [Chapter 9, "Running Banking and Recipient Processes," Setting Up Additional Mandatory Provident Fund Report Details, page 103.](#)

See Also

Appendix A, "Appendix: Global Payroll for Hong Kong Reports," page 157

Chapter 6, "Defining Earnings," Calculating Mandatory Provident Fund Earnings, page 64

Chapter 7, "Defining Deductions," Calculating Mandatory Provident Fund Deductions, page 75

Chapter 8, "Administering Mandatory Provident Fund Contributions," Accommodating MPF Exemption Rules and Limits, page 84

Chapter 8, "Administering Mandatory Provident Fund Contributions," Calculating Permitted Period MPF Contributions, page 91

Chapter 8, "Administering Mandatory Provident Fund Contributions," Calculating Regular MPF Contributions, page 93

Submitting the Remittance Statement

The GPHKMPF1 Remittance Statement enables you to report on mandatory and voluntary MPF contributions that were deducted for the contribution period for the MPF provider. The statement is used to inform the trustee of the amount of MPF contributions paid for relevant employees.

If an employee changes pay groups in the pay period, the employee is reported only once under the most recent pay group. Active employees, excluding those who haven't been enrolled yet (under 18 or less than 60 days employment), are included in the statement even if they have no relevant earnings for the month. Employees with no relevant MPF earnings are included in the existing employees section of the report.

MPF contribution amounts are printed for each type of MPF deduction. Contributions for employees with different contribution periods (such as weekly and monthly) are reported in separate remittance statements.

As it is possible to have multiple pay groups with the same remittance period, you can enter multiple pay groups on the run control.

To provide for reporting terminated employees' MPF contributions, change the calendar payment date to the appropriate date, then run payroll for terminated employees through a group list. Having done this, you can generate the remittance statement for terminated employees because the report is generated by payment date and group list.

However, if you must run it for continuing employees, set the appropriate calendar payment date before running the payroll so that you can generate the report with the regular payment date and regular group list, excluding the terminated group list.

Note. While service providers might specify their own remittance statements, the MPF Authority specifies the content and format of the remittance statement with which the service provider must comply. The remittance statement has, therefore, been defined in accordance with the content and format of the statement specified by the MPF Authority.

The statement is sorted by recipient name (MPF provider), because while in most organisations there is only one provider, it is possible for an organisation to use multiple MPF providers.

Legislation requires the employer to make MPF contributions within 10 days of the employee's termination date during regular periods. Therefore, you must generate the Remittance Statement within 10 days of termination.

Chapter 9

Running Banking and Recipient Processes

This section provides overviews of banking and recipient processing, the Hong Kong banking process flow, and discusses how to:

- Link source banks to pay entities.
- Set up additional Mandatory Provident Fund report details.
- Manage electronic fund transfers (EFT) to recipients.
- Generate recipient payment report files.
- Process manual and separate cheques.

Understanding Banking and Recipient Processing

Global Payroll for Hong Kong supports net payment (employee salary) direct deposits and recipient payments using the electronic file (HSBC) format used by the Hong Kong and Shanghai Corporation Bank. Banking and recipient processing enables you to:

- Run an EFT file creation process to generate a file that includes employee salaries (net payments) and recipient payments.

Net amounts and recipient payments are calculated by the core banking process and stored in the GP_PAYMENT result table.

- Generate data for delivering deduction details to the recipient.

The process extracts payment information directly from the GP_PAYMENT result table to create the HSBC file.

- Decide whether to take the commission out of the recipient payment, as recipients may pay a commission to the pay entity.
- Keep track of your banking and recipient processing, and generate the following reports:
 - Net Payment report: Contains information about amounts transferred to employee accounts.
 - Recipient report: Contains details about amounts collected from employees on behalf of a recipient.

See Also

Appendix A, "Appendix: Global Payroll for Hong Kong Reports," page 157

PeopleSoft Enterprise Global Payroll 9.1 PeopleBook, "Defining Banking Instructions"

Understanding the Hong Kong Banking Process Flow

The Global Payroll banking process brings together payroll data, pay entity source bank data, and payee or recipient bank data. The Hong Kong EFT file creation process extracts data compiled by the banking process according to the type of EFT file that you are creating, merges it with data provided by the Hong Kong country extension, and creates the file for transmission.

Global Payroll handles the banking process as follows:

1. Runs the payroll process using Global Payroll.

This provides the payment data for the banking process.

2. Runs the Global Payroll banking process.

Net amounts and recipient payments are calculated by the core prepayment banking process and stored in the GP_PAYMENT result table. The payment status is set to *P* (prepared). The GP_PAYMENT result table contains one entry for every net pay distribution from every payment included in a calendar run and provides the basis on which an organization pays its payees.

3. Using Global Payroll for Hong Kong, run the Electronic File For Transfers Application Engine process (GPHK_EFT), which populates the HSBC file used for electronic fund transfer.

In this step, the system selects payees from GP_PAYMENT with the following parameters:

- Payment status: *P* (prepared).
- Payment type: *01* (net pay distribution).
- Payment method: *T* (bank transfer).
- Currency code: *HKD*.

The payment status for the selected payees is set to *T* (transferred) in GP_PAYMENT.

Note. You must run the banking process before the HSBC file generation process.

See Also

PeopleSoft Enterprise Global Payroll 9.1 PeopleBook, "Defining Banking Instructions"

Common Elements Used in This Chapter

HSBC	Hong Kong and Shanghai Banking Corporation.
HSBC file	Electronic file format, as described by the Hong Kong and Shanghai Corporation Bank (fixed-length file used for electronic fund transfer).
HSBC EFT data	Single process used to generate the data required for reporting in the EFT format, as defined by HSBC.
Recipient	Any third-party organization that has dealings with the employer using global payroll software.
Net Payment	Payment that includes employee salaries.
Source Bank	Money sources defined at the pay entity level, from which payroll disbursements are drawn. They identify each funding location and the EFT formats used by each institution.

Viewing Delivered Elements

The PeopleSoft system delivers a query that you can run to view the names of all delivered elements designed for Hong Kong. Instructions for running the query are provided in the *PeopleSoft Enterprise Global Payroll 9.1 PeopleBook*.

See Also

PeopleSoft Enterprise Global Payroll 9.1 PeopleBook, "Viewing Delivered Elements," Understanding How to View Delivered Elements

Linking Source Banks To Pay Entities

To link source banks to pay entities, use the Pay Entity Bank Details HKG (GPHK_PYENT_SBNK) component.

After you identify your banks and branches, source banks are the first entities that you create as part of the banking feature in Global Payroll. Source banks identify each funding location and the EFT formats used by that institution.

This section discusses how to link source banks to pay entities.

Page Used to Link Source Banks To Pay Entities

Page Name	Definition Name	Navigation	Usage
Pay Entity Bank Details HKG	GPHK_PYENT_BNK	Set Up HRMS, Product Related, Global Payroll & Absence Mgmt, Framework, Organizational, Pay Entity Bank Details HKG, Pay Entity Bank Details HKG	Link a source bank to a pay entity and define the source bank's customer number that identifies the EFT formats used by that organization.

Linking Source Banks To Pay Entities

Access the Pay Entity Bank Details HKG page (Set Up HRMS, Product Related, Global Payroll & Absence Mgmt, Framework, Organizational, Pay Entity Bank Details HKG, Pay Entity Bank Details HKG).

Pay Entity Bank Details HKG

Pay Entity: G1PEC G1PEC used for GP US

Bank Details
[Customize](#) | [Find](#) | [View All](#) | [First](#) | [1 of 1](#) | [Last](#)

	*Source Bank ID	Account Name	Customer Number		
1	03032	Account 1234567 Name	00291817	+	-

Pay Entity Bank Details HKG page

Pay Entity and Source Bank ID

Link a specific pay entity with the source bank ID that is used to fund all payroll activities for all payees that are part of this pay entity. The system uses these links to:

- Locate (for net payments) source bank IDs and pay entities for the calendar group ID.
- Locate (for recipient payments) source bank IDs and pay entities for the debit date.
- Locate (for both net and recipient payments) the source bank IDs and pay entities for the debit date and the calendar group ID.

Define your source banks and account numbers on the Source Bank Accounts page.

Customer Number

For each source bank ID, identify the appropriate bank or branch customer number (bank reference number). This number identifies the EFT formats used by that institution and is used to generate the name of the electronic file.

The HSBC file name is the first 8 digits of the customer number with the APC file extension. Because HSBC has the profile of all customers, they verify the submitted file with the customer information. If the file is valid, they transfer the funds on the appointed date.

For example, the HSBC customer number for PeopleSoft Hong Kong is 586 2988 023-233. The autopay file for PeopleSoft Hong Kong is 58629880.APC.

See Also

PeopleSoft Enterprise Global Payroll 9.1 PeopleBook, "Defining Banking Instructions," Defining Source Banks

Setting Up Additional Mandatory Provident Fund Report Details

To set up additional Mandatory Provident Fund (MPF) report details, use the Deduction Recipients HKG (GPHK_RCP_CMN) component.

This section discusses how to:

- Set up recipient commission and MPF scheme details.
- Link employees to recipients by membership number.

Pages Used to Set up Additional Mandatory Provident Fund Report Details

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Deduction Recipients HKG	GPHK_RECIPIENT_EXT	Set Up HRMS, Product Related, Global Payroll & Absence Mgmt, Banking, Deduction Recipients HKG, Deduction Recipients HKG	Enter additional recipient information including that required for the MPF Remittance Statement. Additional information must be captured for each MPF scheme. Define the commission calculation method for one or more pay entities and associate each recipient with a file layout name.

Page Name	Definition Name	Navigation	Usage
Add Recipient Mbrship Nbr HKG	GPHK_MEMBERSHIP_NO	Global Payroll & Absence Mgmt, Payee Data, Net Pay / Recipient Elections, Add Recipient Mbrship Nbr HKG, Add Recipient Mbrship Nbr HKG	Link employees to recipients using the employee's membership number.

Setting up Recipient Commission and MPF Scheme Details

Access the Deduction Recipients HKG page (Set Up HRMS, Product Related, Global Payroll & Absence Mgmt, Banking, Deduction Recipients HKG, Deduction Recipients HKG).

Deduction Recipients HKG

Recipient ID: G1GNAZ01

File layout Name: ACCOUNT_CHARTFIELD GL Account Tbl Flat File

Registration Number:

Commission & Scheme Details Customize | Find | View All | | First 1 of 1 Last

Commission **Scheme**

	Pay Entity	Description	Recipient Group Nbr	*Commission Calc Option	*Commission Calc Method	Commission Value		
1	GH3	Hong Kong Business Institute G	<input type="text"/>	Report	None	<input type="text"/>		

Deduction Recipients HKG page

Note. Multiple views of this page are available on the tabs in the scroll area. We document fields common to all views first.

Common Page Elements

File Layout Name Select the appropriate file layout from those you have created in Application Designer for the electronic files you submit to your recipients.

Registration Number This is the MPF reference number and it appears on the MPF Remittance Statement.

Pay Entity Enter the pay entity that is going to receive any commission payable by the recipient. If the commission is to be deducted from the payment due to the recipient, the debit to this pay entity's source bank will be reduced by the commission amount.

Commission & Scheme Details

You can define the commission calculation method for one or more pay entities and associate each recipient with a file layout name.

Commission Tab

Recipient Group Nbr (recipient group number)

When a transaction takes place between the employer and the recipient, it is common to have a unique identification number representing the organization. Enter the unique identifier which the recipient has supplied to your pay entity. For payment to recipients, the group number is part of the unique lodgment reference that is part of each recipient EFT file.

Associate a group number with the pay entity who will remit amounts to the recipient. This unique ID must be captured and maintained for the reports and electronic file supplied to the recipient.

Commission Calc Option (commission calculation option)

Commission is calculated either for reporting or for deducting the calculated amount (from the total amount transferred). Select the method used to calculate fee processing:

Deduct (deduct commission): The system deducts the commission amount from the payment due to the recipient. Select a Commission Calc Method, either flat amount or percentage.

Report (report only): The system reports the commission amount in the EFT file but doesn't deduct it from the payment.

Once a recipient has been identified for processing and the total amount to be paid is known, the system calculates commission (if you have specified it) and deducts the amount or fee from the total amount. This step is carried out only if the setup at the recipient level (for the pay entity) has been set to "calculate and deduct commission."

Commission Calc Method (commission calculation method)

Enter the commission as a percent rate (*Percentage*) or flat amount (*Flat Amt*).

If commission is to be deducted, the appropriate value is calculated and the newly calculated amount is written to the file layout object:

- The flat amount commission payment calculation is:

(Payment Amount) – (Commission Value)

- The percentage amount commission payment calculation is:

(Payment Amount) x (Commission Value)

Commission Value

The flat amount or percentage of the commission to be calculated. If you select *Flat Amt* or *Percent* as the Commission Calc Method, you must enter a value in the Commission Value field.

Note. You should enter the value as a decimal (2 percent as 0.02).

Scheme Tab

The fields in this page are for MPF reporting.

Participation Number, Contact ID, and Contact Phone Just as recipients identify each employer with a group number, they also identify their employees, as a group, with a unique number that is also known as the participation number.

Linking Employees to Recipients by Membership Number

Access the Add Recipient Mbrship Nbr HKG page (Global Payroll & Absence Mgmt, Payee Data, Net Pay / Recipient Elections, Add Recipient Mbrship Nbr HKG, Add Recipient Mbrship Nbr HKG).

Add Recipient Mbrship Nbr HKG

Angela Lee Person ID: CFG0308

Membership Number	Find View All First 1 of 1 Last
Recipient ID: K0BKGR1 Banking - General Receiver 1	
Membership Number:	

Add Recipient Mbrship Nbr HKG page

Recipient ID When a transaction takes place between the employer and the recipient, it is common to have a unique identification number representing the organization. Enter the unique identifier that the recipient has supplied to your pay entity.

Membership Number For reporting, employers must enter their MPF membership details for each of their employees. Just as recipients identify each employer with a group number, they also identify their employees (associated with the employer) with a unique number that is also known as the participation number.

The membership number is used on the reports and electronic file supplied to the recipient.

Managing Electronic Fund Transfers to Recipients

This section provides an overview of the EFT HSBC file and discusses how to manage electronic fund transfers to recipients.


Understanding the EFT HSBC File

The Hong Kong-standard HSBC file for EFT is created by a process that provides multiple options that control what each file contains. You can create an EFT file that contains:

- Net pay data only.

- Recipient data only.
- Net pay and recipient data.

The following diagram shows the tables that contribute data to the HSBC file that is part of the EFT file:



Tables contributing data to the HSBC file

Note. You must finalize your banking process (GP_PMT_PREPARE) before you can create the HSBC file. After the HSBC file has been created, the system changes PMT_STATUS on GP_PAYMENT from *P* (prepared) to *T* (transferred).

Pages Used to Manage Electronic Fund Transfers to Recipients

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Create EFT Payment File HKG	GPHK_EFT_RUNCTL	Global Payroll & Absence Mgmt, Payment Processing, Create EFT Payment File HKG, Create EFT Payment File HKG	Enter run parameters and initiate the Electronic File For Transfers Application Engine process (GPHK_EFT), which creates the EFT file for the bank transfer and the reports. This page enables you to decide whether the EFT file should contain net payment data, recipient payment data, or both.
Net Payment Report HKG	GPHK_NPY_RUNCTL	Global Payroll & Absence Mgmt, Payment Processing, Net Payment Report HKG, Net Payment Report HKG	Generate the Net Payment report that contains information on amounts transferred to employee accounts. Lists the same details that are written to the electronic file (generated for net payments).

Creating the EFT HSBC File

Access the Create EFT Payment File HKG page (Global Payroll & Absence Mgmt, Payment Processing, Create EFT Payment File HKG, Create EFT Payment File HKG).

Create EFT Payment File HKG

Run Control ID: PS [Report Manager](#) [Process Monitor](#) [Run](#)

*Payment Type:

Calendar Group ID: [Bi-Weekly - 1st Pay Period](#)

Payment Date: [Debit Date:](#)

Description:

Recipients List		Customize	Find	View All	First	1 of 1	Last
	Recipient ID	Description					
1	<input type="text" value="GXBKGR5"/>	Banking - General Receiver 5					

Create EFT Payment File HKG page

Payment Type

The EFT file that the system creates contains only payments of the type that you specify. The value that you select here enables you to identify which details are written to the EFT file and determines the other fields that you must complete on this page.

Net Pay Distribution: Enter a calendar group ID and payment date. You don't need to enter a debit date or recipient ID. Only employee salary details (net payments) are processed. The system selects employees with a payment method of bank transfer for the specified calendar group. When processing net payments, multiple pay entities are associated with a single calendar group ID, and there is a distinct EFT file for each pay entity, regardless of whether they use HSBC or some other format.

Recipient Payment: Enter a debit date. You don't need to enter a calendar group ID. Recipient payments are selected. You might be processing payroll weekly but paying the recipient only once per month or quarter. Therefore, if you processed by calendar group ID, you produce only one period of payments for the recipient. This problem is overcome by using the Debit Date field. You can enter the date on which recipients must be paid. The date that you enter is compared to the Debit Date field in the GP_PAYMENT result table. All matching rows for the selected recipient in which the payment type is *Recipient Payment* or *Net Pay and Recipient* are retrieved for processing.

Net Pay and Recipient: Enter a calendar group ID, debit date, and recipient ID.

To process recipients, the payment type can be either *Recipient Payment* or *Net Pay and Recipient*—both are included. Both payments are processed if you select both payment types.

Calendar Group ID	<p>Enter the calendar group ID for which you want the file to be created. This enables you to select a separate pay calendar to pay a smaller group of employees on a different date.</p> <hr/> <p>Note. There is a possibility of using multiple EFT formats to generate the electronic file. There might be multiple pay entities in a single calendar group ID, which means that the process can create separate flat files for each pay entity.</p> <hr/>
Payment Date	<p>Enter the date passed to the EFT file header on which the fund amount is transferred between accounts by the bank. Enter a date regardless of the payment type that you select.</p>
Debit Date	<p>Identifies the recipient transactions that should be selected for processing. The system extracts recipient payments for which the deposit schedule date equals the deposit date.</p>
<i>Recipients List</i>	
Recipient ID	<p>Select recipients to be paid by bank transfer.</p> <p>A recipient is paid only if the payment method in the GP_PAYMENT result table has been identified as <i>T</i> (bank transfer). A recipient identified with a payment method other than bank transfer is not processed, even if selected here.</p> <hr/> <p>Note. Leaving this field blank indicates that a file must be created for all recipients.</p> <hr/>

Generating Recipient Payment Report Files

This section provides an overview of recipient payment files and discusses how to create the recipient payment file.

Understanding Recipient Payment Files

It is common for organizations to transmit a file to a recipient so that they can update their records. For example an organization might pay a recipient weekly and, at the end of the month, deliver a file with all of the payment details. Recipients generally specify the information that they want and the report file layout. After you create the file layout, link it to the recipient on the Deduction Recipients HKG page.

You can select the appropriate file layout from those that you created in PeopleSoft Application Designer for the electronic data (report) files that you submit to your recipients. When you run the creation process, the system creates the file in the layout that you specify here.

PeopleSoft supplies a sample file layout for the recipient file template, GPHK_RCPNT_FILE.

Important! The Application Engine program GPHK_RCPFILE is written to process only the GPHK_RCPNT_FILE recipient schedule file. You can make minor changes to that file, for example field order, but if you make major file layout changes you will need to create additional Application Engine programs to process them.

Pages Used to Generate Recipient Payment Files

Page Name	Definition Name	Navigation	Usage
Create Recipient File HKG	GPHK_RCP_RUNCTL	Global Payroll & Absence Mgmt, Payment Processing, Create Recipient File HKG, Create Recipient File HKG	Generate your recipient payment file. This process stores recipient IDs that should be included during the EFT process for the recipient payment.
Recipient Payment Report HKG	GPHK_RCP_RUNCTL	Global Payroll & Absence Mgmt, Payment Processing, Recipient Payment Report HKG, Recipient Payment Report HKG	Generate the Recipient Payment report, which contains details of amounts collected from employees on behalf of a recipient. The report lists the same details that are written to the electronic file (generated for recipients).

Creating the Recipient Payment File

Access the Create Recipient File HKG page (Global Payroll & Absence Mgmt, Payment Processing, Create Recipient File HKG, Create Recipient File HKG).

Create Recipient File HKG

Run Control ID: PS
[Report Manager](#)
[Process Monitor](#)

Language:

Debit Date:

Recipients List		Customize	Find	View All	First	1 of 1	Last
	Recipient ID	Description					
1	GXBKRG10	GR10					

Create Recipient File HKG page

Debit Date

Enter a date to initiate the process. The process retrieves all recipient payments for which the debit date in the GP_PAYMENT result table equals the debit date that you entered on the Create EFT Payment File HKG page.

The system extracts payment data for which the deposit date equals the date that you enter here.

Recipients List**Recipient ID**

Enter one or more recipient IDs to restrict the number of recipients being processed and reported.

Note. This page should contain the same values that you entered for the generation of the file for bank transfer. A different set of values can lead to generating a file with a totally different set of information. For example, if you ran the bank transfer with a payment date of March 31, 2007 and the recipient payment file is generated for February 28, 2007, the results are not the same. You should use the same run time parameters.

See Also

Chapter 9, "Running Banking and Recipient Processes," Managing Electronic Fund Transfers to Recipients, page 106

Processing Manual and Separate Cheques

This section discusses how to:

- Process manual cheques using calendars.
- Process separate cheques.

Processing Manual Cheques Using Calendars

Organizations are often required to produce manual cheques for their employees. When required, all values are calculated and paid outside of the payroll system. PeopleSoft enables you to enter these values in the system to keep the employee's earning history current.

If a payment to a payee is missed in Global Payroll, enter the values into the pay calendar in which the payment should have occurred. The system recognizes that the pay calendar has been finalized and considers changes made to that calendar during retroactive processing.

To use calendars for manual cheques:

1. Create a new calendar ID and calendar group ID.

If you incorporate into the naming convention of the calendar group ID a notation that the run was specifically for manual cheques, you can identify at the employee level that the payment was not banked.

2. Add or correct the data (through positive input) in the calendar in which the payment should have occurred.

If the amounts have already been calculated and paid, enter these values here and retro process the entered amounts.

3. Run the pay calculation process for the new calendar.
4. Finalize the pay run when you are satisfied that the results are correct.
5. Use the results of the calculation to create and issue the cheque.

Warning! Don't run the banking process. This prevents the payment from being sent to the bank.

Processing Separate Cheques

It is also common for employers to have local agreements that require certain payments to be assigned to a separate cheque number. PeopleSoft enables you to assign additional earnings to a separate cheque number, either on a one-time basis through positive input or on a more permanent basis through additional earnings. When you run the pay calculation process, a separate gross-to-net calculation is performed.

You typically use separate cheque functionality for bonus payments and retro payments, and the result in the pay calculation is a separate gross-to-net calculation.

To process separate cheques in Global Payroll, set up a new calendar, enter positive input, and process the pay run as usual. (Retro payments can be made in separate calendars, but most earnings need a generation control so that they are not processed in the retro run.)

Employees might also request that their net pay, as the result of this separate calculation, be deposited to a different bank account than that of their regular pay. Global Payroll enables employees to have multiple net distribution details, but they are defined by run type. If you defined a run type for regular run type and another for bonus run type, then the employee can nominate a different bank account for each run.

Note. If this method is used to pay into a different bank account, then retro mismatches occur. When retro triggers are processed, you must manually forward the deltas to a target calendar on the Unprocessed Retro Deltas page.

Chapter 10

Printing and Viewing Payslips

This section discusses how to:

- Print payslips.
- Override payslip delivery options.
- View payslips online.

Printing Payslips

This section provides an overview of payslip printing and discusses how to print payslips.

Understanding Payslip Printing

The template that you defined controls the layout of the printed payslip.

You print payslips by calendar group ID. You can restrict the payslips printed from the pay run associated with the calendar group ID.

You can print payslips for:

- An entire calendar group ID.
- Individual payees for the selected calendar group ID.
- Groups of payees in the selected calendar group ID by pay entity, pay group, department, or location.

Viewing Delivered Elements

The PeopleSoft system delivers a query that you can run to view the names of all delivered elements designed for Hong Kong. Instructions for running the query are provided in the *PeopleSoft Enterprise Global Payroll 9.1 PeopleBook*.

See Also

PeopleSoft Enterprise Global Payroll 9.1 PeopleBook, "Viewing Delivered Elements," Understanding How to View Delivered Elements

Page Used to Print Payslips

Page Name	Definition Name	Navigation	Usage
Create/Print Payslips HKG	GPHK_RUNCTL_PSLP	Global Payroll & Absence Mgmt, Payslips, Create/Print Payslips HKG, Create/Print Payslips HKG	Generates the payslip. Note that you must first define the Calendar Group ID to generate the payslip. All groups selected in the Group ID field will automatically be recreated during the payroll run.

Printing Payslips

Access the Create/Print Payslips HKG page (Global Payroll & Absence Mgmt, Payslips, Create/Print Payslips HKG, Create/Print Payslips HKG).

Create/Print Payslips HKG

Run Control ID: PS [Report Manager](#) [Process Monitor](#)

Payslip Generation Details

Calendar Group ID: Calendar Group GD2 Apr01

[Pay Entity List](#)

[Pay Group List](#)

[Department List](#)

[Location List](#)

[Payee List](#)

Internal Sort Order

*Sort Key 1: *Sort Key 2: *Sort Key 3:

Create/Print Payslips HKG page

Calendar Group ID Select the calendar group for which to create payslips.

Pay Entity List, Pay Group List, Department List, Location List, and Payee List If you want to print payslips for select portion of the calendar group, you can print payslips only for selected pay entities, pay groups, departments, locations, or payees by clicking one of these links and selecting those pay entities, pay groups, departments, locations, or payees for which to create payslips.

Sort Key 1, Sort Key 2, and Sort Key 3 You can set up to three sort keys from the following options: *Department*, *Employee Name*, *Location*, *Not Applicable*, *Pay Entity*, or *Pay Group*. If you select *Not Applicable*, the program prints payslips by employee ID.

Overriding Payslip Delivery Options

The default delivery option for all payslips is the internal or external address that you selected when you defined your payslip template. You can set an effective-dated override of that delivery option at payee level using the Payslip Delivery Option HKG page.

Page Used to Override Payslip Delivery Options

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Payslip Delivery Option HKG	GPHK_PSLP_PYE	Global Payroll & Absence Mgmt, Payee Data, Payslips, Payslip Delivery Option HKG, Payslip Delivery Option HKG	Specify an override for the delivery option for a payee.

Viewing Payslips Online

If you license the PeopleSoft Enterprise ePay application, employees can view an online version of the payslip as a self-service transaction. To aid in resolving questions raised by employees about their payslips, the payroll administrator can view employees' self service payslips in an online view that replicates the employees' view. What you see online is based upon the layout defined in your payslip template, just as what you see on the printed payslip is based on the payslip template.

See Also

PeopleSoft Enterprise ePay 9.1 PeopleBook, "Managing Pay Information for Global Payroll," Setting Up View Payslip

PeopleSoft Enterprise ePay 9.1 PeopleBook, "Managing Pay Information for Global Payroll," Viewing Payslips Online

Chapter 11

Managing Off-Cycle Payments for Hong Kong

This chapter provides an overview of the off-cycle processing and discusses how to:

- Record manual payments for Hong Kong.
- Enter corrections for Hong Kong.
- Make unscheduled payments for Hong Kong.
- Advance payrolls for Hong Kong.

Note. Please refer to the *PeopleSoft Enterprise Global Payroll 9.1 PeopleBook* for information on off-cycle setup and processing.

See Also

PeopleSoft Enterprise Global Payroll 9.1 PeopleBook, "Managing Off Cycle Processing"

Understanding Off-Cycle Processing

This section discusses:

- The off-cycle process.
- Types of off-cycle transactions.
- Viewing of delivered elements.

The Off-Cycle Process

Off-cycle processing refers to processing payments and making corrections to payroll results outside of the normal payroll schedule. Off-cycle transactions are usually made to correct prior payments, enter manual payments, or to make early termination payments that can't wait until the next scheduled payroll.

Types of Off-Cycle Transactions

The four types of off-cycle transactions are:

1. Manual payments

Manual payments enable you to enter payments that you have calculated and paid outside of the payroll system. Examples include paying a new hire with a manual check, because their pay details were not entered in time for the normal pay run.

2. Corrections

Corrections enable you to correct results of any finalized payroll. Examples include reversing a sick leave payment when workers compensation should have been paid.

3. Unscheduled payments

Unscheduled payments enables you to enter one-time payments that fall outside the normal payroll process. Examples include one time bonuses or expense reimbursement.

4. Advances

Advances enables you to pay payees before their normally scheduled pay run. Examples include salary due on termination.

Viewing Delivered Elements

The PeopleSoft system delivers a query that you can run to view the names of all delivered elements designed for Hong Kong. Instructions for running the query are provided in the *PeopleSoft Enterprise Global Payroll 9.1 PeopleBook*.

See Also

PeopleSoft Enterprise Global Payroll 9.1 PeopleBook, "Viewing Delivered Elements," Understanding How to View Delivered Elements

Recording Manual Payments for Hong Kong

This section provides an overview of recording manual payments and provides examples of how to use the manual payment functionality with the Hong Kong delivered rules.

Manual Payments

When entering manual payments for Hong Kong payees, it is recommended that all calculations be manually calculated outside the system and then entered. The following areas need to be considered when entering manual payments:

- Selecting the *Period (Calendar) Paid* and *Payment Date* on the Period Calendar tab of the Manual Payments page.

The selection of the period paid and payment date need to be considered carefully. When selecting the period paid, it is recommended that you select the previous finalized calendar or the current open calendar. The selection of the payment date directly affects how elements are accumulated. For example, if you have an accumulator that accrues based on period end date, the payment date may not update the accumulator balances at the right time.

- Selecting processing controls on the Manual Payments page.

The *Period Begin Date* and *Period End Date* should default after selecting the *Period (Calendar) Paid*. It is recommended that these dates not be changed as the delivered Hong Kong rules have been designed to calculate using whole periods, and may not automatically segment if a partial period is entered.

The run type defaults from the *Period (Calendar) Paid* and it is recommended that the default be used. To ensure that the payee's manual payment is processed by the system, the *Allow Duplicates* check box must be selected on the run type; otherwise, the payee may not be processed again if the system detects that they have already been processed in the period.

Stop Regular Resolution enables you to stop the resolution of all elements on the process list except the elements entered into the manual payment. If you decide to allow regular resolution, an analysis would need to be performed to understand the impact on your supporting elements.

If using the Limited Element Set, you need to ensure that all elements calculate independently of pre- or post-processing formulas, as these do not resolve during off-cycle processing.

Note. Manual payments are used to record monetary values only, absence accumulators will not be updated using this method.

Entering Corrections for Hong Kong

This section provides an overview of corrections and provides examples of how to make corrections using the Hong Kong delivered rules.

Corrections

The Corrections page of the Off-Cycle Requests component (GP_OFFCYCLE_SETUP) is used when you need to change finalized results, usually due to a user error. This method uses period-to-date logic built into the Hong Kong delivered statutory rules.

The following areas need to be considered when entering corrections:

- All earnings and deductions need to have period-to-date logic applied.
- This method is used to correct pay accumulators only. Absence accumulators will not be corrected.

Making Unscheduled Payments for Hong Kong

This section provides an overview of unscheduled payments and provides examples of how to make unscheduled payments using the Hong Kong delivered rules.

The Unscheduled Payments page of the Off-Cycle Requests component (GP_OFFCYCLE_SETUP) is used to make one-time payments that are processed outside of the on-cycle payroll. Examples include bonuses and expense reimbursements. This method uses period-to-date logic built into the Hong Kong delivered statutory rules when calculating.

The following areas need to be considered when entering unscheduled payments:

- All earnings and deductions need to have period-to-date logic applied.
- When selecting the period paid, it is recommended that you select the previous finalized calendar or the current open calendar.
- This method is used to record monetary values only. Absence accumulators will not be updated.

Advancing Payrolls for Hong Kong

This section provides an overview of advance payrolls and provides examples of how to make advance payrolls using the Hong Kong delivered rules.

The Advance Payrolls page of the Off-Cycle Requests component (GP_OFFCYCLE_SETUP) is used when you would like to pay an employee before their normal on-cycle pay run. For example an employee is terminating employment with your organisation, and the termination payment needs to be paid immediately and not in the next on-cycle pay run. The following is recommended when making advance payments:

- Always select the next open calendar, as skipping calendars may update accumulators incorrectly.
- Absence accumulators will calculate automatically for the calendar group selected.

Note. Advance Payroll does not replace Pay in Advance functionality used for Hong Kong absences.

Chapter 12

Processing Inland Revenue Reports

This chapter provides an overview of processing Hong Kong Inland Revenue (IR56) reports and discusses how to:

- Generate Inland Revenue report data.
- Review and maintain IR56 report data.
- Generate the IR56B electronic file.
- Run Inland Revenue reports.

Understanding Hong Kong Inland Revenue Reporting

You must generate several reports to comply with Hong Kong legislative payroll requirements. These reports are statutory and report the following information:

- *IR56B*: Employer's return of remuneration and pensions.
- *IR56E*: Notification by employer of an employee commencing work.
- *IR56F*: Notification by employer of an employee about to cease employment.
- *IR56G*: Notification by employer of an employee about to depart Hong Kong.
- *IR56M*: Notification of remuneration paid to persons other than an employee.

We discuss all aspects of the creation of the data for these Inland Revenue reports. This includes all of the pages that enable, generate, and maintain both employee and company identification and biographical data that support the reporting requirements of the Hong Kong Inland Revenue Department (IRD).

To ensure that you populate all of the available details required for your Inland Revenue reports, it is important that you follow the correct sequence of steps:

1. Set up report data using the following pages:
 - Report Element Setup.
 - Departure Details.
 - Principal Employer of PT EE.
 - Employee Housing Quarters.
 - Self Employed Data.
 - Overseas Concern Details.
 - IR56 Creation Controls HKG.
 - Tax Reference Number Details.
 - IR56 Exchange Rate Definition.
2. Generate IR56 report data using the Create IR56 Data HKG page.
3. Review and maintain IR56 report data using the following pages:
 - IR56 Personal Details.
 - IR56 Job / Quarters Details.
 - IR56 Monetary Details.
4. Generate IR56 reports using the Print pages for each of the reports (IR56B, IR56M, IR56E, IR56F and IR56G).
5. Generate the IR56B Electronic File using the IR56 Electronic File Creation page.

Note. Inland Revenue reports also use personal data, such as spouse details and national IDs. You can check this information after you run the reports using the IR56 Personal Details page.

See Also

[Chapter 12, "Processing Inland Revenue Reports," page 123](#)

Generating Inland Revenue Report Data

This section provides an overview of the Inland Revenue Report data creation process and discusses how to generate the IR56 report data.

Understanding the Inland Revenue Report Data Creation Process

The Inland Revenue Report data creation process generates data for all Inland Revenue reports. The Inland Revenue Department has defined the report layout and the conditions that must be met while generating the IR56 reports. These conditions affect the way in which you generate and store the data in PeopleSoft tables.

The GPHK_IR56_TBL table stores the results of the data generated by the data creation process. This data is used for viewing and generating the IR56B electronic file and hard copy reports.

Note. The IR56 creation program maintains the creation date. During the printing of IR56 documents, if the system identifies a document as a replacement, the system retrieves the date when it created the earlier version and uses that as the submission date.

Viewing Delivered Elements

The PeopleSoft system delivers a query that you can run to view the names of all delivered elements designed for Hong Kong. Instructions for running the query are provided in the *PeopleSoft Enterprise Global Payroll 9.1 PeopleBook*.

See Also

PeopleSoft Enterprise Global Payroll 9.1 PeopleBook, "Viewing Delivered Elements," Understanding How to View Delivered Elements

Page Used to Generate Inland Revenue Report Data

Page Name	Definition Name	Navigation	Usage
Create IR56 Data HKG	GPHK_IR56_CREATE	Global Payroll & Absence Mgmt, Year-End Processing, Create IR56 Data HKG, Create IR56 Data HKG	Run the process that captures information required for generating IR56 data and reports. After the process is initiated, the system identifies eligible employees and retrieves the information required for reporting.

Generating IR56 Report Data

Access the Create IR56 Data HKG page (Global Payroll & Absence Mgmt, Year-End Processing, Create IR56 Data HKG, Create IR56 Data HKG).

Create IR56 Data HKG

Run Control ID: ps [Report Manager](#) [Process Monitor](#) [Run](#)

*Tax Reference Number: (A)1234567 Hong Kong Business Institute

*Tax Year: 2006 ☐ Recreate

*Report Type: Select Report To Process ▼

Begin Date: 01/01/2006 End Date: 12/31/2006 Creation Date: 10/18/2006

Selected Employee List for IR56				Customize Find View All		First	1-2 of 2	Last
	EmplID		Name					
1	0002		Susan Jones					
2	0004		Atif Ovedara					

Create IR56 Data HKG page

Tax Reference Number Select the tax reference number representing the pay entity (or entities) for which the IR56 must be generated. IR56 reports all run by tax reference number, which has a major impact on the way the system creates and stores IR56 data. For every employee attached to the pay entity (sharing the tax reference number), the system combines amounts for each year to date element by currency code and stores them in the IR56 result tables. After the process is completed, you can use the IR56 Monetary Details page to enter adjustments to reflect the amount that should be reported on the IR56 documents.

Tax Year Enter the period for which the report must be reported. Hong Kong has set the tax period to be April 1 to March 31. Enter the year with 4 digits (for example, 2006).

Note. Although the tax year is not required for the IR56G and IR56F reports, you must still enter it.

Recreate

When you run the IR56 generation process for the first time, the value of this field does not matter. Data is generated for the selected employees or all eligible employees of the pay entity.

When you initiate the process again with the same parameters, the Recreate check box determines the following:

If you select the check box:

- Employees (records in the IR56 table) that belong to the select group are deleted if the document created earlier has not been issued. Manual changes or information entered on the employee record using the IR56 Inquiry component are retained and included in the new record created for the employees.
- If employees have been issued the respective document, a new employee record is generated on top of the existing one. The newly created record is identified as a replacement record. Manually entered information in the earlier version is copied into the new record.

If you deselect the check box, records are generated for the select group only if they don't already have a record existing. The record created is identified as an original record.

Note. The select group is the employee list entered on the run control page or the employees that are selected based on the criteria entered on the run control page for a specific pay entity.

Begin Date and End Date

These fields are required for the IR56F, IR56G, and IR56E reports. They enable you to narrow down the criteria of employee for whom the report should be generated. The begin and end dates are the tax period for which the employee received a particular amount.

For an IR56F, employees whose termination dates occur during the specified date range are selected.

For an IR56G, employees whose departure dates from Hong Kong occur during the specified date range are selected.

For an IR56E, employees whose hire dates occur during the specified date range are selected.

Unlike the IR56B and IR56M reports, in which balances for employees must be retrieved as of the end of the year, balances in this case are retrieved as of the period end date. The process identifies the last finalized pay calendar that is closest to the period end date and retrieves the balances for reporting.

Selected Employee List for IR56

EmplID (employee identification)

You can initiate the data creation process for a specific set of employees by selecting one or more employees.

Although you can select an employee ID, the process still decides if an employee is eligible to receive the selected IR56 document. For example, if you are running the process to create IR56B and you select an employee who has been terminated, the process ignores this employee.

Working with Report Types

Report Type	Processing
Annual Return For Employees IR56B	<p>Employees who are active at the end of the tax year are selected for processing. Active employees are identified by their employee status. Values are:</p> <p>A: Active. P: Leave with pay. Q: Retired with pay. U: Terminated with pay.</p> <p>The value is matched with the current row in the JOB record for the employee. Because an employee can have multiple jobs, the status is checked against all of the job records for the employee being processed. An employee is considered active when at least one job record matches the previously mentioned employee status.</p>
Annual Return For Non-Employee IR56M	Non-employees who are active at the end of the tax year are selected for processing. The same processing as IR56B occurs.
Notify Employee Departing HKG IR56G	Employees whose dates of departure from Hong Kong are during the period that you specify are selected for processing. Although this report is more likely for terminated employees, the process does not search for the employee status of the employee. The process ensures that the employee has not been issued an IR56B or IR56F for the same period of employment.
Notifying New Employee IR56E	Employees whose hire dates are during the period that you specify are selected for processing. Although this report is more likely for terminated employees, the process does not search for the employee status of the employee. The process ensures that the employee has not been issued an IR56B or IR56F for the same period of employment.

<i>Report Type</i>	<i>Processing</i>
Notifying Terminating Employee IR56F	<p>Employees who have been terminated during the period are selected for processing. Employees are considered terminated when all the concurrent jobs associated with their EmplIDs have been terminated.</p> <p>The Employee Status field in the JOB record identifies whether an employee is active or inactive. Valid employee status values to identify terminated employees are:</p> <p>A: Active.</p> <p>P: Leave with pay.</p> <p>Q: Retired with pay.</p> <p>U: Terminated with pay.</p> <p>An employee is considered inactive when all the job records match the previously mentioned employee status. The process ensures that the employee has not been issued an IR56B or IR56G for the same period of employment.</p>

Note. The employee status is only one of the parameters used to determine whether the employee is eligible to receive an IR56 report. The second parameter is the YTD balance that is maintained by payroll.

Reviewing and Maintaining IR56 Report Data

This section provides an overview of Inland Revenue reporting generated data inquiry pages and discusses how to:

- Maintain IR56 personal details.
- Maintain IR56 monetary details.

Understanding Inland Revenue Reporting Generated Data Inquiry Pages

After you set up and generate the data required for Inland Revenue reporting and generate those forms, you can review the results and maintain available fields. The IR56 Inquiry component enables you to view and amend the generated IR56 data.

To access the component, enter the specific Inland Revenue report type, tax year, run number, employee ID, or pay entity. The inquiry pages display the information generated for an employee for specific report types. The fields on these inquiry pages contain three types of values:

- Values generated from related tables that you cannot modify.
- Values that you can enter only on the inquiry page because there is no way of calculating the value.

- Values generated by the IR56 data creation process, which you can override by entering an adjustment amount.

The adjustment amount is captured and maintained in a separate field.

Pages Used to Review and Maintain IR56 Report Data

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
IR56 Personal Details	GPHK_IR56_INQ1	Global Payroll & Absence Mgmt, Authority Correspondence, Review/Update IR56 Data HKG, IR56 Personal Details	View the IR56 details generated for the employee and review an employee's personal information including their identification details, spouse details and address history.
IR56 Job / Quarters Details	GPHK_IR56_INQ2	Global Payroll & Absence Mgmt, Authority Correspondence, Review/Update IR56 Data HKG, IR56 Job / Quarters Details	View the IR56 details generated for the employee. This page provides job-related and housing quarter information provided to the employee including country departure and employee residence quarters details. The employee residence quarters details default from the details you set up on the Employee Housing Quarters page. The country departure details default from the details you set up on the Departure Details page.
IR56 Monetary Details	GPHK_IR56_INQ3	Global Payroll & Absence Mgmt, Authority Correspondence, Review/Update IR56 Data HKG, IR56 Monetary Details	View the IR56 details generated for the employee and enter employee monetary and tax details. Specific group boxes for each report type also appear.

Maintaining IR56 Personal Details

Access the IR56 Personal Details page (Global Payroll & Absence Mgmt, Authority Correspondence, Review/Update IR56 Data HKG, IR56 Personal Details).

IR56 Personal Details		IR56 Job / Quarters Details		IR56 Monetary Details	
EmplID:	KH0010	Xue Lim			
Run Number:	0	*Issue Status:	Issued		
Tax Year:	2004	Begin Date:	04/01/2003		
Report Type:	Notifying Terminating Employee		End Date:	01/19/2004	
Gender:	Female				
Marital Status:	Married				
Employee Identification Detail					
National ID:	KK5556765				
Passport Number:					
Employee Spouse Details					
Name:	Lim,Bim				
National ID:	FE2343123				
Passport Number:	3269546				
Address History					
Find View All First 1 of 1 Last					
Country:	<div>HKG</div> <div>Hong Kong</div>				
Address:	<div>RM 565</div> <div>TAI TUNG HOUSE</div> <div>48 HENNESSY ROAD</div> <div>Hong Kong Island, WAN CHI</div> <div>Edit Address</div>				

IR56 Personal Details page

Issue Status

Displays the level of the report. The value is *Not Issued* when the process generates the data, but the printing process has not been completed. When you run the printing process, the value changes to *Issued*. To stop a particular record from being processed, select *On Hold*. This status stops both the electronic file process and the printing process from processing the record.

You can also change the status back to *Not Issued*.

Electronic File Status

If you are creating an IR56B for an employee after you have sent the electronic file to the IRD, there are additional records that weren't included in the initial file. The new electronic file status is *Supplementary*. The status of the initial file is *Sent*.

Employee Identification Detail and Employee Spouse Details

In addition to employee details, statutory reports must report details of the employee's spouse. The Workforce Administration menu in Human Resources provides the Dependent Information (DEPEND_BENEF) and Depdnt Identification Details (IDENTIFICATN_DEP) components to maintain spouse details.

Name Displays the employee's full name details. The Name History page in Workforce Administration enables you to enter employee names in non-English characters. You can enter names in Chinese and English at the same time in separate fields.

PeopleSoft enables you to enter employee names in alternate characters. This feature is available in the Workforce Administration - Personal Details component in Human Resources.

Note. The Chinese name is used in correspondence with the Inland Revenue Board and is used on the employee's payslip.

National ID It is necessary to store the employee and spouse Hong Kong Identity Card (IC) numbers or Tax File Numbers. This information is used in correspondence with the Inland Revenue Department. It is also necessary to store the Identity Card numbers of the employee's dependants.

The details are retrieved from the National ID table (PERS_NID) under Personal Data. The DEP_BENEF_NID table contains different IDs for an employee's spouse.

Passport Number Displays the employee or spouse passport number (required for noncitizens). The CITIZEN_PSSPRT table contains passport details of both employees and their dependants.

Address History

Edit Address To change any of the default address details, click this link to access the Edit Address page.

Maintaining IR56 Monetary Details

Access the IR56 Monetary Details page (Global Payroll & Absence Mgmt, Authority Correspondence, Review/Update IR56 Data HKG, IR56 Monetary Details).

IR56 Personal Details		IR56 Job / Quarters Details		IR56 Monetary Details	
Xue Lim		Person ID:		KH0010	
Run Number:		0			
Tax Year:		2004			
Report Type:		Notifying Terminating Employee			
Total Amount		Find View All First 1 of 3 Last			
IR56 Report Element:		01 Salary / Wages			
Accumulators associated with Report Element		Customize Find View All First 1 of 1 Last			
	Element Name	Begin Date	End Date	Adjustment Amount	Amount
	1 BASSAL_FYTDA				36290.32
					HKD
					36290.32
					Amount: 36290.32
Comments:					
Tax Amount paid by Employer:		0.00		Begin Date:	End Date:
Payments by Overseas Concern					
Overseas Concern Identifier:					
Amount Paid (in HID):		HKD			
Enter -ve amount for Unknown:					
IR56F Specific Details					
Amount Not Declared But Paid:		0.00			
Name of New Employer:					
Address of New Employer:					
Future Correspondence Address:					

IR56 Monetary Details page

Total Amount**IR56 Report Element and Element Name**

Displays predetermined categories that appear in Inland Revenue reports.

Associate payroll accumulators (element names) that must be reported against an IR56 report element instead of rerunning payroll to populate the accumulators.

Associate payroll accumulators with IR56 report elements on the IR56 Report Data HKG page.

Begin Date and End Date	Displays the dates during which the element and accumulator link are effective. <hr/> Note. These fields are editable if the issue status not <i>Issued</i> . <hr/>
Adjustment Amount, Amount, and Currency	The first instance of the Amount field displays the amount calculated by the data creation process (in HKD) and it initially appears identically in two other locations in the group box. The first field remains the same, regardless of any adjustments (element additions or subtractions) you make. Instead of modifying this generated amount, you enter additional adjustment rows which enable you to add or subtract any additional amounts (in any currency) not calculated during the initial data creation process. You can enter amounts to add or negate a value generated by the process for an accumulator associated with a report element. For example, if you have to subtract 300 USD from the initial amount because the employee has been temporarily employed by a different pay entity, enter – (minus) 300 in the Adjustment Amount field and select <i>USD</i> as the Currency in the new row. The amount in the Amount field at the bottom of the Total Amount group box automatically adjusts by subtracting the equivalent of 300 USD and displaying the new total. Similarly, if you want to add 300 USD, enter 300 in the Adjustment Amount field. <hr/> Note. The Adjustment Amount field is editable if the issue status not <i>Issued</i> . <hr/> The IR56 creation process supports multiple currency processing which impacts the way year to date values are processed and stored in the IR56 result table. In addition to entering manual adjustments, you can enter the currency code in which you are paying the amount. The process calculates the value in local HKD currency and displays the amount reported on the IR56 reports.
Tax Amount paid by Employer	Displays the amount of taxes paid by an employer for an employee. This information is needed for IR56 reporting.

Payments by Overseas Concern

If the employee received an amount from an overseas concern, select the organization that made the payment and enter the amount.

Overseas Concern Identifier	Select the code used to track the overseas concern. Define the overseas concern name and identifier on the Overseas Concern Details page.
Amount Paid (in HID) and Enter -ve amount for Unknown	Enter the amount paid by the overseas concern to the employee and select the currency for the amount (it can be any currency that is defined in the system). If the amount is unknown, enter any negative amount (– 400).

IR56E/F/G/M Specific Details

For each report type that you select, an additional group box appears, enabling you to enter details specific to the report.

See Also

Chapter 4, "Setting Up Inland Revenue Reports," Linking Accumulators with Report Elements, page 22

Generating the IR56B Electronic File

This section provides an overview of flat file generation and discusses how to generate the IR56B electronic file.

Understanding Flat File Generation

PeopleSoft provides the ability to create a flat file that complies with Hong Kong Inland Revenue Department requirements for the submission of electronic files. The output is created by an Application Engine process using a file layout object that has the same structure as that of the electronic file expected by the IRD of Hong Kong.

The employees are selected from the GPHK_IR56_TBL table and records from GPHK_IR56_TBL, GPHK_IR56_QTR, and GPHK_IR56_DTL are retrieved and processed. During the process, personal information, spouse details, and identifications details are also retrieved and the file layout object GPHK_IR56B is populated.

Page Used to Generate the IR56B Electronic File

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Create IR56B Elec File HKG	GPHK_IR56_EFILE	Global Payroll & Absence Mgmt, Year-End Processing, Create IR56B Elec File HKG, Create IR56B Elec File HKG	Create a flat file that complies with Hong Kong Inland Revenue Department requirements for the submission of electronic files.

Generating the IR56B Electronic File

Access the Create IR56B Elec File HKG page (Global Payroll & Absence Mgmt, Year-End Processing, Create IR56B Elec File HKG, Create IR56B Elec File HKG).

Create IR56B Elec File HKG

Run Control ID: PS
[Report Manager](#)
[Process Monitor](#)

*Tax Reference Number: (A)1234567

*Tax Year: 2006

Creation Date: 10/18/2006

Hong Kong Business Institute

☐ Test Run

Create IR56B Elec File HKG page

Tax Reference Number IR56 reports run by tax reference number, which has a major impact on the way the system creates and stores IR56 data. For every employee attached to the pay entity (sharing the tax reference number), the system combines amounts for each year to date element by currency code and stores them in the IR56 result tables. After the process is completed, you can use the IR56 Monetary Details page to enter adjustments to reflect the amount that should be reported on the IR56 documents.

Tax Year Displays the period for which the report must be created. Hong Kong has set the tax period to be April 1 to March 31.

Note. Although the tax year is not required for the IR56G and IR56F reports, you must still enter it.

Test Run Select this check box to create (but not send) the electronic file, so that you can view and check your data. When selected, employee records are not marked as sent and the supplementary status is not applicable.

Running Inland Revenue Reports

There are several statutory reports that you must generate to comply with Hong Kong legislative payroll requirements. The data creation process must be run before running these reports.

- The *IR56B* is an annual report generated for tax declaration purposes. A summary of the earnings and deductions for each employee is reported in a predetermined format. The information is also generated in a predetermined electronic file format and submitted electronically.
- The *IR56M* is a report of candidates, other than employees, who received remuneration at a period in time (for a given tax year) and are about to cease employment in a given period of time.
- The *IR56G* is a report on employees who are about to depart from Hong Kong. All tax liabilities are to be settled before the employee's departure.

- The *IR56F* is a report of employees who are about to cease employment in a given period of time. You are not required to submit the report if a terminated employee is about to depart Hong Kong. Instead, you should submit an IR56G report.
- The *IR56E* is a report that lists employees who have joined the organization in a given period of time. It must be sent within three months from the date of commencement of employment.

Note. As companies are split into multiple pay entities, the reports display the company name and not the pay entity name. For example, the company name could be Brentworth Holdings and incorporate the following pay entities—Brentworth Holdings Aeronauticals Ltd., Brentworth Holdings Catering Ltd., and Brentworth Holdings Aviation Services. The IR56 report displays Brentworth Holdings as the reporting name.

Pages used to Run Inland Revenue Reports

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
IR56B Report HKG	GPHK_IR56B_RUNCTL	Global Payroll & Absence Mgmt, Year-End Processing, IR56B Report HKG, IR56B Report HKG	Generate the IR56B (GPHK0001) — Employer's Return of Remuneration and Pensions report.
IR56M Report HKG	GPHK_IR5M_RUNCTL	Global Payroll & Absence Mgmt, Year-End Processing, IR56M Report HKG, IR56M Report HKG	Generate the IR56M (GPHK0002) — Notification of remuneration paid to persons other than an employee report.
IR56E Report HKG	GPHK_IR56E_RUNCTL	Global Payroll & Absence Mgmt, Authority Correspondence, IR56E Report HKG, IR56E Report HKG	Generate the IR56E — Notification by Employer of an Employee commencing work report.
IR56F Report HKG	GPHK_IR56FG_RUNCTL	Global Payroll & Absence Mgmt, Authority Correspondence, IR56F Report HKG, IR56F Report HKG	Generate the IR56F — Notification by Employer of an Employee about to cease employment report.
IR56G Report HKG	GPHK_IR56FG_RUNCTL	Global Payroll & Absence Mgmt, Authority Correspondence, IR56G Report HKG, IR56G Report HKG	Generate the IR56G — Notification by Employer of an Employee about to depart Hong Kong report.

Chapter 13

Defining Absence Rules

This chapter provides overviews of absence rules for Hong Kong, delivered absence primary elements and discusses how to:

- Calculate annual leave.
- Calculate absence entitlements on termination.
- Calculate sick leave.
- Calculate maternity leave.
- Calculate leave without pay (LWOP).
- Calculate other leave.

Understanding Absence Rules for Hong Kong

This section discusses absence rules for Hong Kong.

Global Payroll for Hong Kong delivers predefined rules for processing absence payments, such as annual leave, long service leave, sick leave, maternity leave, and jury leave. Rules are also delivered to calculate absence entitlements on termination, including rules for the payment of unused annual leave, 13th month payment, outstanding deduction recovery, severance, and long service.

PeopleSoft designed these rules in accordance with Hong Kong statutory requirements. You can modify many of these rules to reflect absence and termination policies that are specific to your organisation or to labor agreements with your employees.

To demonstrate how Global Payroll can process typical absence requirements in Hong Kong, PeopleSoft provides 8 absence entitlement elements and 10 absence take elements. After the table of primary elements—the absence and take elements—we describe the interaction of each element with supporting elements.

Note. For the customary data discussed in this chapter, two categories of employees are identified: *Statutory* and *General*. Each category has its own customary data (absence entitlement, take rules, and accrual rules).

See Also

PeopleSoft Enterprise Global Payroll 9.1 PeopleBook, "Entering and Processing Absences"

PeopleSoft Enterprise Global Payroll 9.1 PeopleBook, "Defining Absence Elements"

PeopleSoft Enterprise Global Payroll 9.1 PeopleBook, "Understanding Absence Management"

Common Elements Used in This Chapter

Leave Without Pay (LWOP)	Unpaid absence type.
Maternity Leave (MLV)	Paid confinement period.
Sick Leave (SLV)	Paid sick period.
Annual Leave (ALV)	Paid absence type.
Other Leave (OLV)	Paid or unpaid absence type subjected to organisation decision.
Long Service Payment (LSP)	Payment made when termination occurs after a long period of service.
General Employees	Employees employed on a permanent basis.
Statutory Employees	Employees employed on an hourly and contract basis.

Understanding Delivered Absence Primary Elements

This section discusses the delivered absence elements.

Primary absence elements are absence entitlements—entitlement or proration and absence takes. In the following tables, we cross-reference entitlements to takes and takes to entitlements in the description column. After the following tables, we discuss each element in detail.

This section discusses:

- Absence entitlements elements.
- Absence take elements.

Absence Entitlements Elements

The following table lists the Absence Entitlement elements for Hong Kong.

Name	Description and Used By
Annual Leave	
ALV GENL ENT	Genl (general) annual leave entitlement ALV GENL TKE
ALV STAT ENT	Stat (statutory) annual leave entitlement ALV STAT TKE
Jury Leave	
OLV JURY ENT	Jury entitlement OLV JURY TKE
Compassion Leave	
OLV COMP ENT	Compassion entitlement OLV COMPASS TKE
Marriage Leave	
OLV MARR ENT	Marriage entitlement OLV MARRIAGE TKE
Maternity Leave	
MLV MAT ENT	Maternity entitlement MLV GENL TKE and MLV STAT TKE
No Paid Leave	
NPL LWOP ENT	No paid leave entitlement NPL LWOP TKE
Sick Leave	

Name	Description and Used By
SLV SICK ENT	Sick leave entitlement SLV GENL TKE and SLV STAT TKE

See Also

PeopleSoft Enterprise Global Payroll 9.1 PeopleBook, "Entering and Processing Absences"

PeopleSoft Enterprise Global Payroll 9.1 PeopleBook, "Defining Absence Elements"

PeopleSoft Enterprise Global Payroll 9.1 PeopleBook, "Understanding Absence Management"

Absence Take Elements

The following table lists the Absence Take elements for Hong Kong.

Name	Description and Take Uses
Annual Leave	
ALV GENL TKE	Genl annual leave take ALV GENL ENT
ALV STAT TKE	Stat annual leave take ALV STAT ENT
Jury Leave	
OLV JURY TKE	Jury take OLV JURY ENT
Compassion Leave	
OLV COMPASS TKE	Compassion leave take OLV COMP ENT
Marriage Leave	

Name	Description and Take Uses
OLV MARRIAGE TKE	Marriage leave take OLV MARR ENT
Maternity Leave	
MLV GENL TKE	Genl maternity leave take MLV MAT ENT
MLV STAT TKE	Stat maternity leave take MLV MAT ENT
Leave Without Pay	
NPL LWOP TKE	Leave without paid take NPL LWOP ENT
Sick Leave	
SLV GENL TKE	Genl sick leave take SLV SICK ENT
SLV STAT TKE	Stat sick leave take SLV SICK ENT

Note. For Hong Kong, the unit for absence entitlement, take, and accrual is *day*. While half-day absence is allowed, a quarter day or the hours of absence are generally not accepted. All absence types except maternity leave can take half-day leave. The service date is used as the default base for the absence accrual process. The anniversary date for absence and termination is derived from the service date.

Note. Female payees are eligible for statutory maternity leave. If your organization or location, however, has a policy to provide leave benefits for male employees whose wives have just given birth, it is possible to provide them with maternity leave benefits as the system does not check the payee's gender.

See Also

PeopleSoft Enterprise Global Payroll 9.1 PeopleBook, "Entering and Processing Absences"

PeopleSoft Enterprise Global Payroll 9.1 PeopleBook, "Defining Absence Elements"

PeopleSoft Enterprise Global Payroll 9.1 PeopleBook, "Understanding Absence Management"

Viewing Delivered Elements

The PeopleSoft system delivers a query that you can run to view the names of all delivered elements designed for Hong Kong. Instructions for running the query are provided in the *PeopleSoft Enterprise Global Payroll 9.1 PeopleBook*.

See Also

PeopleSoft Enterprise Global Payroll 9.1 PeopleBook, "Viewing Delivered Elements," Understanding How to View Delivered Elements

Calculating Annual Leave

An employee is entitled to annual leave after working 12 months for one employer, and then for each succeeding 12 month period. The following annual leave rules are delivered for general and statutory employees.

This section provides overviews on absence forfeiture, leave accrual, and discusses how to:

- Calculate annual leave for general employees.
- Calculate annual leave for statutory employees.

See Also

Chapter 6, "Defining Earnings," Calculating Annual Leave Instead of Annual Leave Entitlement, page 60

Understanding Absence Forfeiture

This section provides an overview on absence forfeiture.

Annual leave can be carried forward to the next 24 months and compensation is not paid for forfeited annual leave. There is no limitation for statutory employees; the annual leave balance is always carried over to the next year. However, for general employees, the annual leave balance can be carried forward only to the next 24 months.

Understanding Leave Accrual

This section discusses leave accrual.

The accrual process for annual leave occurs once per month. Run this process before pay calculation. For general employees, prorated entitlement is added to the entitlement balance after the monthly accrual process is finished.

For example, an employee is hired on April 15, 2006 and is entitled to 12 days of annual leave per year. The annual leave entitlement at the end of the first month is:

$$16 / 30 \times 12 / 12$$

If the entitlement increases after a set number of years of service, such as an additional one day, annual leave is awarded when finishing the first year of service. In this case, the employee in the anniversary period gains:

(14 / 30 × 12 / 12) last years entitlement plus (16 / 30 × 13 / 12) new entitlement (effective from the first anniversary day).

For statutory employees, absence accrual runs annually during the anniversary month. For example, if an employee is hired in January 2006, then the first annual absence accrual process is January 2007. After the first accrual, the employee earns seven days of entitlement.

Calculating Annual Leave for General Employees

The annual leave entitlement ALV GENL ENT, using formula ALV FM GENL ENT, returns the monthly annual leave entitlement during the monthly accrual process. Use the annual leave in lieu earning ANN LIEU to pay unused annual leave for termination or payment.

The ALV FM GENL ENT formula resolves as follows:

1. The annual leave entitlement value is retrieved from bracket ALV BR GENL ENT.

The yearly entitlement is deannualised whenever the entitlement has not been changed during the pay period. If the entitlement has been changed, the partial entitlements before and after the anniversary date are added and returned.

2. The current year's annual leave entitlement variable CM VR CUR ENT stores the current deannualised annual leave entitlement.

The previous year's annual leave entitlement variable CM VR PRV ENT stores the previous deannualised annual leave entitlement.

3. The duration CM DR YR OF SERV returns the employee's years of service (number of years between the service date SERVICE DT and the pay period end date PERIOD END DATE).
4. The formula ALV FM PREV ACCM returns the previous year's balance (system variable PREV VALUE ACCM) and is used in the accumulator initialize rule.
5. The annual leave balance accumulator ALV GENL ENT_BAL is carried forward to the new annual leave accumulator.

Whenever the accumulator begins, the previous accumulator balance is brought to the current balance (new accumulator period).

6. The variables, CM VR ANNIV MTH (begin month) and CM VR ANNIV DY (begin day) specify the begin date of the accumulators.

All accumulator periods are year to date (YTD) and begin to accumulate from the employee's hire date.

7. The formula ALV FM GENL FORFEIT returns the forfeited units that are eventually reduced from the annual leave balance accumulator.

The formula ALV FM GENL ADJUST returns the forfeiture unit. This formula checks the current year's entitlement plus last year's entitlement and forms a forfeiture level. For example, an employee is entitled to 7 days in the first year, 8 days in the second, and 9 days in the third year. During the second year of service, the employee's annual leave balance cannot exceed 15 days, and it cannot exceed 17 days during the third year of service.

Calculating Annual Leave for Statutory Employees

The accrual process runs once for every 12 month period from the employee's hire date. The annual leave entitlement ALV STAT ENT, using formula ALV FM STAT ENT, returns the annual leave entitlement for statutory employees, only when their anniversary dates occur in the current pay period. The formula also returns annual leave entitlement from the employee's last anniversary date to the termination date only when the employee is terminated in the current pay period.

The ALV FM STAT ENT formula resolves as follows:

1. The annual leave entitlement value is retrieved from bracket ALV BR STAT ENT.
2. The current year's annual leave entitlement variable CM VR CUR ENT stores the current deannualised annual leave entitlement.

The previous year's annual leave entitlement variable CM VR PRV ENT stores the previous deannualised annual leave entitlement.

3. The duration CM DR YR OF SERV returns the years of service (number of years between the service date SERVICE DT and the pay period end date PERIOD END DATE).
4. The formula ALV FM PREV ACCM returns the previous year's balance (system variable PREV VALUE ACCM) and is used in the accumulator initialize rule.
5. The annual leave balance accumulator ALV STAT ENT_BAL is carried forward to the new annual leave accumulator.

Whenever the accumulator begins, the previous accumulator balance is brought to the current balance (new accumulator period).

6. The formula ALV FM STAT FORFEIT returns the forfeited units that are eventually reduced from the annual leave balance accumulator.
7. The generation control ALV GC ANNIV MTH controls the entitlement by resolving only when the employee's anniversary month equals the pay period month.
8. The formula ALV FM ANNIV MTH resolves when GP PRD END DATE MO (variable that stores the *mm* part of the pay period end date) equals CM VR ANNIVMTH (variable that stores the payee's *mm* part of the hire date) and the employee is not hired in the current pay period.
9. The variables CM VR ANNIV MTH and CM VR ANNIV DT specify the accumulator's begin date.

All accumulator periods are YTD and begin to accumulate from the employee's hire date.

Calculating Absence Entitlements on Termination

PeopleSoft delivers a set of predefined rules for processing absences due to termination. PeopleSoft designed these rules in accordance with Hong Kong statutory requirements.

This section discusses how to:

- Calculate unused annual leave.
- Calculate 13th month payment.
- Calculate severance and long service leave payments.
- Pay outstanding deduction recovery upon termination.

Note. The system element TERMINATION DT in the employment record is populated when you select an action reason of either *Retirement* or *Termination* on the Job page. They are both considered termination. Action *Termination* with a reason of *Redundancy* or *Layoff* is considered job redundancy. If the employee is terminated with one these reasons and has worked more than two years, then the employee is entitled to severance payment.

See Also

Chapter 6, "Defining Earnings," Calculating Absence and Termination Earnings, page 60

Calculating Unused Annual Leave

When general and statutory employees are terminated after three months of continuous service, they are entitled to a payment for their prorated unused annual leave. The earning element ANN LIEU is the payment in lieu of annual leave entitlement. The calculation of the unused annual leave amount is $\text{Unit} \times \text{Rate}$:

- Unit is set by the unused annual leave balance in days formula: TER FM ALV BAL.
- Rate is set by the average daily rate formula: CM FM DAILY RATE.

$$(\text{Average Daily Rate}) = (\text{Average Monthly Earning}) / 30$$

Note. The constant 30 represents the number of days in a month and is also used in February (28 or 29 days) or March (31 days).

The TER FM ALV BAL and CM FM DAILY RATE formulas resolves as follows:

1. The system checks the service date system element TER DATE to determine whether the terminated payee is eligible to receive a payment instead of unused annual leave.

The date CM DT PROBATION is three months after the service date.

2. The actual annual leave balance for termination calculation is returned by formula TER FM ALV BAL, using ALV GENL ENT_BAL for general employees and ALV STAT ENT_BAL + current year (up to the termination date) balance.
3. The value is returned to the earning element ANN LIEU and is then multiplied by the average daily rate calculated by CM FM DAILY RATE.

Use ANN LIEU to pay employees when they accept payments from their employer to offset part of the annual leave. This is a positive input and the unit of ANN LIEU is overridden by the number of adjusted days from the annual leave balance. ANN LIEU is a taxable earning element. Therefore, it contributes to the annual taxable accumulator.

Note. An employee can have a negative annual leave balance when processing unused leave during the termination process. The outstanding balance should be converted to monetary value and paid back to the employer. The calculation of the outstanding annual leave is the same as the unused annual leave.

See Also

Chapter 6, "Defining Earnings," Calculating Annual Leave Instead of Annual Leave Entitlement, page 60

Calculating 13th Month Payment

Regular 13th month payment is an additional payment of basic salary (normally 100 percent of regular) paid to employees a few days before the Chinese New Year. If the employee is eligible for 13th month pay and is terminated, then prorated payment is paid even if the employee was hired on or after the cut-off date (assuming that the employee has completed the probation period of three months of service). Some organisations set the cut-off period to stop current yearly 13th month pay if the employee was hired on or after the previous year's cut-off date.

To pay 13th month payments, use the TER 13TH PAY earning element attached to the TER SE MAIN section. The 13th month payment is calculated as $\text{Base} \times \text{Percent}$:

- Base is set by the formula TER FM 13TH PAY.
- Percent is 100.

The TER FM 13TH PAY formula resolves as follows:

1. If the employee is hired and terminated in the same year (when variable CM VR SERV YR equals variable OE VR CAL YEAR) or if the employee is hired on or after the previous year's cut-off date and terminated in the current year (when the SERVICE DT is on or after the variable OE VR CUT OFF DT), then the following specific elements are included in the calculation:
 - A: Duration from hire date to termination date (using duration TER DR DY IN SERV).
 - B: Calendar days in termination year—either 365 or 366 (using duration OE DR DAYS IN YR).
 - C: Basic salary as of termination date (using MONTHLY RT).
2. The prorated 13th month pay is calculated as $A / B \times C$.

3. If the employee is hired before the previous year's cut-off date and is terminated in the current year, the following additional element is incorporated into the preceding calculation:

D: Duration from January 1 of the termination year to the employee's termination date (using duration TER DR DY LAST YR).

4. The prorated 13th month pay is calculated as $D / B \times C$.

The duration TER DR MTH IN SERV determines the total number of service months between the employee's hire date and termination date. If this is fewer than three months, no payment is made. The date OE DT CAL YEAR extracts the current calendar year.

The service date must be on or after the 13th month pay cut-off date OE VR CUT OFF DT.

See Also

Chapter 6, "Defining Earnings," Calculating the Thirteen Month Pay, page 58

Chapter 6, "Defining Earnings," Calculating 13th Month Payment on Termination, page 63

Calculating Severance and Long Service Leave Payments

An employer should pay severance payment when an employee who has been employed under a continuous contract for not less than 24 months is dismissed by reason of redundancy. Customary data with the following rules pays severance payments when:

- The employee has worked for the company for more than 24 months.
- The termination action is redundancy (*terminated with benefit*).

The calculation rule for both severance and long service payments is the same. Employees can receive only severance payment or long service payment, but not both. An employer should pay long service payment to an employee who is employed not less than five years under a continuous contract, and who:

- Is not dismissed due to serious misconduct.
- Dies.
- Resigns due to ill health.
- Retires early or at age 65 or above.

The formula TER FM LSP PAYMT (severance and LSP amount) returns the severance payment or long service payment, depending on the employee's year of service and the termination action reason.

The TER FM LSP PAYMT formula resolves as follows:

1. The years of service and maximum claim amount for the terminated employee are retrieved from bracket TER BR LSP ENT.

The formula TER FM LSP PERIOD is used as the search key for the bracket.

2. The variable TER VR MAX LSP stores the maximum claimable LSP amounts that are stored in the bracket TER BR LSP ENT.

The variable TER VR LSP CEILING stores the maximum ceiling of average wages (currently 15000 HKD).

3. The duration CM DR MTH OF SERV returns the number of months between the service date SERVICE DT and the pay period end date GP PRD END DT plus one.

The duration CM YR OF SERV NDEC returns the years of service with no decimals.

4. The variable OE VR ROLL UNIT is needed before it calls the formula OE FM ROLL AVG.
5. The formula OE FM ROLL AVG obtains the employee's average earning and calculates the employee's payment using the following formula:

$$\text{LSP} = (\text{Average Earning} \times 2/3) \times (\text{Reckonable Years of Service})$$

The factor 2/3 is a constant factor defined by the Hong Kong Labor Department. The formula first checks the monthly average earning and multiplies it by 2/3 (0.67). The result cannot be greater than the maximum ceiling of 15000 HKD, which is also defined by the Labor Department. The total is then multiplied by the employee's reckonable years of service stored in the bracket TER BR LSP ENT. If it exceeds 15000 HKD, then 15000 HKD is returned and multiplied by the employee's reckonable years of service.

See Also

Chapter 6, "Defining Earnings," Calculating Severance and Long Service Payments, page 62

Paying Outstanding Deduction Recovery Upon Termination

The earning element CASHADV is a cash advance that is paid in advance to an employee. The total amount of the advance must then be paid back to the organisation in several installments. The outstanding cash advance balance is stored in the goal amount (balance) accumulator. When the termination occurs, the system checks the goal amount accumulator and resolves the whole goal amount during the last pay period.

The CASHADVR recovery deduction is always 20 percent of the CASHADV, and the recovery ceases to resolve when the cash advance goal balance accumulator CM AC GOAL BAL equals zero.

When the employee is terminated, the whole cash advance goal balance should be recovered in the last pay period, so the deduction amount of the CASHADVR is overridden by the cash advance goal balance accumulator. A negative net balance is allowed when the net amount is not enough to recover the whole goal balance.

See Also

Chapter 6, "Defining Earnings," Calculating Cash Advances, page 59

Chapter 7, "Defining Deductions," Calculating Cash Advance Recovery, page 74

Calculating Sick Leave

This section provides an overview of sick leave and discusses how to calculate sick leave payments.

Understanding Sick Leave

One sick leave entitlement SLV SICK ENT (formula SLV FM ENT) for both general and statutory employees is delivered as customary data. The sick leave balance is always carried over to the next period, but the balance cannot exceed 120 days.

Statutory Employees

The employer should pay statutory employees sickness allowance if the employee takes sick leave of no less than four consecutive days. Only a percentage of the employee's daily wage is paid. Uncertified sick leave or zero balance sick entitlement is considered LWOP. To pay sick leave for statutory employees, also use the DY WAGE 80 earning element and take SLV STAT TKE.

General Employees

Employees can take half or more days of paid sickness only when they have enough balance. For an approved sickness, they receive 100 percent of their normal daily wages. Uncertified sick leave or zero balance sick entitlement is considered LWOP. To pay sick leave for general employees, also use the take SLV GENL TKE.

Calculating Sick Leave Payments

The formula SLV FM ENT returns sick leave entitlement if the employee is not terminated during the pay period. When the employee is terminated during the pay period, the formula returns either zero or the SLV BR ENT bracket value, which eventually returns the monthly sick entitlement (two or four days) to the terminated employee.

The SLV FM ENT formula resolves as follows:

1. The bracket SLV BR ENT stores the monthly sick entitlement.

The system checks the bracket and attempts to resolve the sick entitlement. The prorated entitlement is not returned, but the lower is returned from the bracket. For example, 1.9 months of service returns 2 from the bracket. Sick leave accrual is run on each pay period and during the accrual process.

2. The adjustment formula SLV FM ADJUST adjusts the exceeded sick leave balance when it reaches 120 days.

It evaluates the system element ABS END ENTL BAL if it is greater than 120, then returns the exceeded unit to offset the sick leave balance.

3. The formula SLV FM PREV ACCM returns the system element PREV VALUE ACCM, which stores the value of the old accumulator.

This formula is used in the accumulator initialization to bring the old balance to the new accumulator.

4. The formula SLV FM ENT returns sick leave entitlement if the employee is not terminated during the pay period.

When termination occurs during the pay period, the formula returns either zero or the SLV BR ENT bracket value, which eventually returns the monthly sick entitlement (two or four days) to the terminated employee.

5. The absence day formula CM FM TKE UNIT evaluates each day of the absence event.

The required entitlement units (either 1 or 1/2) of each absence date are returned and compared with the beginning entitlement balance to calculate the paid and unpaid units. If PARTIAL HOURS is greater than half of SCHED HRS, it is treated as a one-day leave of absence.

6. For statutory employees, take SLV STAT TKE generates the earning element DY WAGE 80 for every paid sick leave, which calculates 80 percent of the employee's average earning.

The earning element uses formula CM FM DAILY WAGE to return the employee's daily wage, which is calculated by the formula OE FM ROLL AVG.

Calculating Maternity Leave

This section provides an overview of maternity leave and discusses how to calculate maternity leave.

Understanding Maternity Leave

The following rules are delivered as customary data for maternity leave:

- Employees are eligible if they worked no less than 40 weeks.
- A maximum of 10 weeks of paid maternity leave is granted, if eligible.

Alternative holiday is not granted if statutory or public holidays occur during the maternity period.

- Statutory employees receive 80 percent of the average earning, and general employees receive 100 percent of the basic salary.
- Employees cannot take a half-day of maternity leave.

Calculating Maternity Leave

The maternity leave entitlement MLV MAT ENT is delivered for all employees and is granted when the leave occurs (per absence). The PAID maternity period is 70 days from the maternity commencement date. Absence periods longer than 70 days are considered LWOP.

The maternity leave calculation resolves as follows, using the MLV FM MAT ENT and MLV FM RESOLVE ENT formulas:

1. The date MLV DT ELIG (maternity eligible date), in conjunction with the ABSENCE DATE, specifies the date that must be reached before the maternity absence can be paid.

The date is 40 weeks after the hire date (service date SERVICE DT). If the date of the absence is earlier than the maternity eligible date, no payment is made.

2. The formula MLV FM MAT ENT returns 1 if the employee has reached the maternity eligible date.
3. The conditional resolution formula MLV FM RESOLVE ENT resolves if the absence date is fewer than 70 days and does not resolve to use the existing entitlement balance.

The formula returns one SCHED HRS entitlement for each absence date.

Because there is always no entitlement balance for maternity, the required entitlement units of maternity leave longer than 70 days are considered LWOP.

4. The formula MLV FM RESOLVE ENT uses duration MLV DR MAT to determine the duration in days between the absence begin date and absence date.

It determines if the maternity absence date is paid or unpaid.

5. The take MLV STAT TKE generates the earning element DY WAGE 80 for statutory employees, which calculates 80 percent of the employee's average earning.

The earning element uses formula CM FM DAILY WAGE to return the employee's daily wage, which is calculated by the formula OE FM ROLL AVG. For general employees, MLV GENL TKE, no positive input is generated because the employees are paid 100 percent of basic salary.

6. The absence day formula CM FM TKE UNIT evaluates each day of the absence event.

The required entitlement units (either 1 or 1/2) of each absence date are returned and compared with the beginning entitlement balance to calculate the paid and unpaid units. If PARTIAL HOURS is greater than half of SCHED HRS, it is treated as a one-day leave of absence.

Calculating Leave Without Pay

This section provides an overview of leave without pay and discusses how to calculate leave with pay.

Understanding Leave Without Pay

There are no entitlement and accruals associated with LWOP. The following rules are delivered:

- LWOP can be taken from the employee's hire date.
- One daily rate (Annual Basic Salary / 365) is deducted from monthly pay for every single LWOP taken during the pay period.

Note. The LWOP2 earning element is used for leave without pay for hourly rates (for weekly employees—as it uses an hourly rate).

- A half-day can be taken.

Statutory Employees

Annual leave cannot be taken if the employee has not earned it. When the accrual balance for annual leave is not enough to cover the whole duration of annual leave, the difference is considered LWOP.

General Employees

Annual leave can be taken if the employee has not earned it.

See Also

Chapter 6, "Defining Earnings," Calculating Leave Without Pay (LWOP), page 61

Chapter 6, "Defining Earnings," Calculating Leave Without Pay (LWOP2), page 62

Calculating Leave Without Pay

The NPL LWOP ENT (no paid leave entitlement) is delivered for both general and statutory employees. LWOP can be taken anytime during the servicing period. One daily basic rate is deducted from the employee's salary for every single day of LWOP. The value of one daily basic rate equals the annual salary divided by 365 (even in a leap year).

The LWOP calculation is $\text{Unit} \times \text{Rate}$:

- Unit is set at the payee level.
- Rate is the system variable DAILY RT (daily rate).

LWOP pay is calculated as follows:

1. The system element DAY COUNT UPD notifies the system to generate earnings for the UNPAID unit only.

The total amount is subtracted from the employee's basic salary when the employee takes the LWOP (per absence). A zero entitlement is granted when the LWOP occurs.

2. The take NPL LWOP TKE uses the day formula CM FM TKE UNIT to determine if the absence date requires entitlement.
3. The earning element LWOP is generated for each day of LWOP using the conditional resolution formula CM FM RESOLVE ENT.

This returns one SCHED HRS entitlement for each absence date.

Calculating Other Leave

This section provides an overview of other leave and discusses how to calculate other leave.

Understanding Other Leave

Three types of other leave are delivered as customary data for Hong Kong:

- Jury.
- Compassion.
- Marriage.

Note. Examination leave and study leave are considered LWOP.

Calculating Other Leave

There are no entitlements for other leave types and no accruals are associated with them. Employees are paid when the absences occur. Although jury, compassion, and marriage leave have similar entitlement and take setup, marriage leave requires completion of an eligibility period of three months. To handle this, a date CM DT PROBATION is defined, which is three months after the service date. The formula OLV FM MARR ENT resolves if the employee has finished the probationary period and returns zero if the employee is under probation.

Other leave is calculated as follows:

1. The variables CM VR ANNIV MTH and CM VR ANNIV DT notify the system when the accumulators should start to accumulate.

During the initialization session, the payee's hire date is retrieved and the *ddmm* part of the date is extracted and assigned to these variables.

2. The date element CM DT HIRE stores the payee's hire date, then passes the *mm* part of the date to CM VR ANNIV MTH and the *dd* part of the date to CM VR ANNIV DT during the absence initialization.
3. A day formula CM FM TKE UNIT determines each absence date from the absence event (if it is a rest day or a working day).

The formula returns zero for rest days and returns one or half-day if the absence date is a working day.

4. The system uses a conditional resolution formula CM FM RESOLVE ENT that resolves if it is a working day and doesn't resolve if it is a rest day.

No further conditions are required before the entitlement is resolved for all other leave types.

5. Although the entitlement setup for all other leave types is identical, each leave type has its own set of accumulators.

The entitlement formulas OLV FM ENT or OLV FM MARR ENT pay one or half-days of entitlement, which are then resolved whenever the absence occurs. All accumulator periods are YTD accumulators and begin to accumulate from the employee's hire date.

6. The takes for each of the other leave types use the day formula CM FM TKE UNIT to determine whether the absence date requires entitlement.

Only the date CM DT PROBATION is used to specify the eligibility date for marriage leave.

Appendix A

Appendix: Global Payroll for Hong Kong Reports

The tables in this appendix list the Global Payroll for Hong Kong reports sorted alphanumerically by report ID. There is additional information about some report run control pages within the chapter for particular features.

Note. For samples of these reports, see the PDF files published on CD-ROM with your documentation. You can print all of the reports in the Hong Kong official language: Traditional Chinese.

Global Payroll for Hong Kong Reports: A to Z

This section provides detailed information on individual reports.

Mandatory Provident Fund Reports

<i>Report ID and Report Name</i>	<i>Description</i>	<i>Navigation</i>	<i>Run Control Page</i>
GPHKEE01 Employee New/Terminated	Enables you to report on new and terminated employees. The report is not specific to MPF and has the general purpose of reporting new and terminated employees. Depending on the report type you select, the program will generate either a new or terminated employee report.	Global Payroll & Absence Mgmt, Authority Correspondence, Employee New - Terminated Rpt HKG	GPHK_EE01_RC
GPHKMPF1 MPF Remittance Statement	Enables you to report on mandatory and voluntary MPF contributions that were deducted for the contribution period for the MPF provider. Used to inform the trustee of the amount of MPF contributions paid for relevant employees.	Global Payroll & Absence Mgmt, Authority Correspondence, MPF Remittance Statement HKG	GPHK_MPF1_RC

Recipient Payment Reports

Report ID and Report Name	Description	Navigation	Run Control Page
GPHKEFT1 Net Payment Report	Contains information on amounts transferred to employee accounts. Lists the same details that are written to the electronic file (generated for net payments).	Global Payroll & Absence Mgmt, Payment Processing, Net Payment Report HKG	GPHK_NPY_RUNCTL
GPHKEFT2 Recipient Payment Report	Contains details of amounts collected from employees on behalf of a recipient. Lists the same details that are written to the electronic file (generated for recipients).	Global Payroll & Absence Mgmt, Payment Processing, Recipient Payment Report HKG	GPHK_RCP_RUNCTL

Inland Revenue - Legislative Reports

Report ID and Report Name	Description	Navigation	Run Control Page
GPHKIRR1 - IR56B Employer's Return of Remuneration and Pensions	Provides an annual report generated for tax declaration purposes. It includes a summary of the earnings and deductions for each employee, reported in a predetermined format. The information is also generated in a predetermined electronic file format and submitted electronically.	Global Payroll & Absence Mgmt, Year-End Processing, IR56B Report HKG	GPHK_IR56B_RUNCTL
GPHKIRR2 - IR56M Notification of Remuneration Paid to Persons Other Than an Employee	Reports on candidates other than employees who received remuneration during a period for a given tax year and are about to cease employment. You must run the data creation process before running this report.	Global Payroll & Absence Mgmt, Year-End Processing, IR56M Report HKG	GPHK_IR5M_RUNCTL

Report ID and Report Name	Description	Navigation	Run Control Page
GPHKIRR3 - IR56E Notification by Employer of an Employee Commencing Work	Lists employees who joined the organisation during a period. It must be sent within three months of the date on which employment commenced.	Global Payroll & Absence Mgmt, Authority Correspondence, IR56E Report HKG	GPHK_IR56E_RUNCTL
GPHKIRR4 - IR56F Notification by Employer of an Employee About to Cease Employment	Reports on employees who are about to cease employment during a period. You must run the data creation process before running this report. You are not required to submit the report if a terminated employee is about to depart Hong Kong. Instead, you should submit an IR56G report.	Global Payroll & Absence Mgmt, Authority Correspondence, IR56F Report HKG	GPHK_IR56FG_RUNCTL
GPHKIRR5 - IR56G Notification by Employer of an Employee About to Depart Hong Kong	Reports on employees who are about to depart from Hong Kong. All tax liabilities are to be settled before the employee's departure.	Global Payroll & Absence Mgmt, Authority Correspondence, IR56G Report HKG	GPHK_IR56FG_RUNCTL

Payslip Report

Report ID and Report Name	Description	Navigation	Run Control Page
GPHKPYSL Hong Kong Payslip	Lists payee details of period earnings, taxes and other deductions, leave balances, and payment distributions.	Global Payroll & Absence Mgmt, Payslips, Create/Print Payslips HKG	GPHK_RUNCTL_PSLP

Index

A

absence

- annual leave, calculating 144
- annual leave, calculating for general employees 145
- annual leave, calculating for statutory employees 146
- annual leave, unused 147
- calculating earnings 60
- common definitions 140
- entitlement elements 140
- entitlements on termination 147
- leave without pay, calculating 61, 153
- leave without pay, weekly employees 62
- maternity leave, calculating 152
- maternity leave, eighty percent earnings 61
- other leave, calculating 154, 155
- overview 139
- payslip 42
- primary elements 140
- sick leave, calculating 151
- sick leave, eighty percent earnings 61
- take elements 142

Absence Details page 37, 42

accommodation, rent reimbursement 57

accumulators

- linking accumulators to report elements 22
- payslip 37
- rolling average calculation 66

Accumulators page 37

Add Recipient Mbrship Nbr HKG page 104, 106

age eligibility rules, Mandatory Provident Fund (MPF) 85

allowances

- black rain 54
- cash advance 59
- education 57
- for mobile phone and pager 56
- housing 56
- meal 54
- shift 53
- typhoon 54

annual leave in lieu, termination 60

Annual Return For Employees *See* IR56B

Annual Return For Non-Employee *See* IR56M

B

banking

- EFT HSBC file 106
- electronic fund transfers 106
- HSBC file 108
- manual and separate cheques 112
- process flow 100
- processing overview 99
- recipient details 104
- recipient membership number 106
- recipient payment report files 110

source banks 101

BASHLY *See Also* basic hourly

basic hourly, calculating 52

basic salary, calculating 51

BASSAL *See Also* basic salary

benefit, housing allowance 56

black rain

allowance 54

calculating 54

business processes, summary 3

C

cash advance

allowance 59

calculating 59

recovery, calculating 74

casual employee contributions, Mandatory

Provident Fund (MPF) 88

community chest

calculating 74

donate to charity 74

compensation

black rain 54

typhoon 54

component names, earnings and deductions 11

contribution holiday rule, overview 85

country set up, retro processing 15

Create/Print Payslips HKG page 116

Create EFT Payment File HKG page 108

Create IR56B Elec File HKG page 135

Create IR56 Data HKG page 125

Create Recipient File HKG page 111

D

daily rate deduction, leave without pay 76

Deduction Recipients HKG (GPHK_RCP_CMN)

component 103

Deduction Recipients HKG page 103, 104

deduction recovery

See Also cash advance, recovery calculating

deductions

cash advance recovery 74

community chest 74

defining 71

generation control 76

Mandatory Provident Fund 77

overview 71

recovering cash advance upon termination 150

Define IR56B/M Controls HKG page 32

Define PT EE Main Employer HKG page 26

Define Self Employed Data HKG page 30

delivered elements

absence entitlements 140

absence takes 142

creating 5

- deductions 71
- earnings 48
- formulas used in rolling average calculation 67
- Mandatory Provident Fund (MPF) deductions 75
- Mandatory Provident Fund (MPF) earnings 64
- Mandatory Provident Fund (MPF) statutory and customary deductions 82
- naming convention 8
- ownership and maintenance 6
- variables used in rolling average calculation 67
- viewing 6

E

earnings

- absence, annual leave in lieu 60
- absence, eighty percent of wages 61
- absence, leave without pay 61
- allowances, cash advance 59
- allowances, education 57
- allowances, housing 56
- allowances, meal 54
- allowances, shift 53
- allowances, typhoon and black rain 54
- basic hourly 52
- basic salary 51
- calculating for absence 60
- calculating for termination 60
- controlling maximum frequency amount 68
- controlling maximum goal amount 69
- defining 47
- elements 49
- flat amounts 63
- formula based amounts 64
- gratuity 57
- Mandatory Provident Fund 64
- nontaxable meal reimbursement 55
- nontaxable mobile and pager allowance 56
- overtime 52
- overview 48
- rent reimbursement 57
- rolling average calculation 65
- scheduling using generation control 69
- subsetting 48
- termination, severance and long service 62
- thirteenth month pay 58

Earnings and Deductions page 37, 40

Edit Address page - Specify Housing Quarters HKG 27

education allowance

- calculating 57
- earnings 57

EFT *See* electronic fund transfer (EFT)

EFT HSBC file, overview 106

eighty percent of daily wages 61

electronic file, IR56B 135

Electronic File For Transfers Application Engine process (GPHK_EFT) 100

electronic fund transfer (EFT)

- HSBC file 108
- to recipients 106

elements *See Also* delivered elements

- component name for earnings and deductions 11
- deductions 71

- earnings 49
- element type codes 12
- functional area codes 11
- ownership, categories 6
- ownership, overview 7
- entitlements, absence termination 147
- exemption rules and limits, Mandatory Provident Fund (MPF) 84
- expense, meal reimbursement 55

F

- flat amounts, earnings 63
- forfeiture, absence 144
- formula based amounts, earnings 64
- formulas, rolling average 67
- functional area codes 11

G

general employees

- annual leave 145
- leave without pay 153
- maternity leave 152
- sick leave 151
- unused annual leave 147

generation control

- cash advance recovery 74
- scheduling deductions 76
- scheduling earnings 69

GPHK_EFT process 100

GPHK_IR56_EXCH_TBL component 33

GPHK_IR56REP_SETUP component 22

GPHK_OVSEAS_CNCRN component 30

GPHK_PSLP_MSG component 44

GPHK_PSLP_SETUP component 36

GPHK_PYENT_SBNK component 101

GPHK_PYGRP_PSLP component 43

GPHK_RCP_CMN component 103

GPHK_TAXREF_TBL component 32

GPHKEE01 report 157

GPHKEFT1 report 108, 158

GPHKEFT2 report 111, 158

GPHKIRR1 - IR56B report 158

GPHKIRR2 - IR56M report 158

GPHKIRR3 - IR56E report 159

GPHKIRR4 - IR56F report 159

GPHKIRR5 - IR56G report 159

GPHKMPF1 report 157

GPHKPYSL report 159

gratuity

- calculating 57
- earnings 57

H

housing allowance

- calculating 56
- earnings 56

HSBC file, creation 108

I

- implementation, table loading 2
- Inland Revenue
 - employee departure details 24
 - exchange rate details 33
 - generating IR56B electronic file 135
 - generating report data 124
 - maintaining IR56 report monetary details 132
 - maintaining IR56 report personal details 130
 - reporting overview 21, 123
 - reports 136
 - report types 128
 - reviewing and maintaining IR56 report data 129
 - setting up employee housing quarters 26
 - setting up overseas concern details 30
 - setting up self employment data 30
 - setting up starting sheet numbers 31
 - tax reference number 32
- IR56B Report HKG page 137
- IR56E Report HKG page 137
- IR56 Exchange Rate Defn HKG component (GPHK_IR56_EXCH_TBL) 33
- IR56 Exchange Rate Defn HKG page 34
- IR56F Report HKG page 137
- IR56G report 24
- IR56G Report HKG page 137
- IR56 Job / Quarters Details page 130
- IR56 Monetary Details page 130, 132
- IR56M Report HKG page 137
- IR56 Personal Details page 130
- IR56 Report Data HKG component (GPHK_IR56REP_SETUP) 22
- IR56 Report Data HKG page 22

L

- leave accrual, overview 144
- leave without pay
 - calculating 61, 153
 - daily rate deduction 76
 - LWOP 61
- Link to Pay Group HKG component (GPHK_PYGRP_PSLP) 43
- Link to Pay Group HKG page 43
- long service leave
 - earnings 62
 - termination 149
- LWOP *See* leave without pay

M

- Mandatory Provident Fund (MPF)
 - common definitions 78
 - maximum and minimum limits 89
 - overview 77
 - permitted period termination rules 87
 - recipient commission and MPF scheme details 104
 - recipient membership number 106

- statutory and customary 82
- Mandatory Provident Fund (MPF), employee
 - 18th birthday proration rule 81
 - 65th birthday proration rule 81
 - age eligibility rules 85
 - contribution holiday rule 85
 - excluding 88
 - exemption rules and limits 84
 - hire and rehires 80
 - included earnings 64
- Mandatory Provident Fund (MPF), employee contributions
 - casual employee 88
 - mandatory permitted period 92
 - permitted period 91
 - regular 95
 - voluntary 96
- Mandatory Provident Fund (MPF), employer
 - permitted period contributions 92
 - regular contributions 94
 - regular voluntary contributions 95
- Mandatory Provident Fund (MPF), employer and employee
 - calculating deductions 75
 - contributions 77
 - proration 80
 - regular contributions 93
 - voluntary permitted period contributions 93
- Mandatory Provident Fund (MPF), remittance statement 97
- manual and separate cheques, banking 112
- maternity leave, calculating 152
- maximum frequency amount, earnings 68
- maximum goal amount, earnings 69
- meal
 - calculating allowance 54
 - calculating reimbursement 55
- messages, payslip 44
- Messages HKG component (GPHK_PSLP_MSG) 44
- Messages HKG page 44
- mobile phone allowance, calculating 56
- monetary details, IR56 132
- MPF *See* Mandatory Provident Fund (MPF)

N

- Net Payment report (GPHKEFT1) 108
- Net Payment Report HKG page 108
- Notify Employee Departing HKG *See* IR56G
- Notifying New Employee Commencing Work *See* IR56E
- Notifying Terminating Employee *See* IR56F

O

- off-cycles
 - advance payrolls 122
 - corrections 121
 - manual payments 120
 - processing overview 119
 - unscheduled payments 122
- one-off payment, gratuity 57
- Overseas Concern Details HKG component

(GPHK_OVSEAS_CNCRN) 30
 Overseas Concern Details HKG page 31
 Overseas Concern Details page, setting up 30
 overtime, calculating 52

P

pager allowance, calculating 56
 pay entities, source banks 101
 Pay Entity Bank Details HKG
 (GPHK_PYENT_SBNK) component 101
 Pay Entity Bank Details HKG page 102
 pay groups, payslip templates 43
 payments
 recipient report files 110
 retro 15
 payslip
 absence details 42
 accumulators 37
 creating templates 36
 delivery options 117
 earnings and deductions 40
 messages 44
 overview 35
 viewing online 117
 Payslip Delivery Option HKG page 117
 permitted period
 employee contributions 92
 Mandatory Provident Fund contributions 91
 Mandatory Provident Fund termination rules 87
 Personal Details, IR56 report 130
 PIN_TYPE *See* element type codes
 primary elements
 naming 12
 naming convention 8
 principal employers, part time employees 26
 printing, payslip 115
 processing manual and separate cheques 112
 proration
 rules 19
 thirteenth month pay 58
 Proration, Mandatory Provident Fund (MPF) 80

R

Recipient Payment report (GPHKEFT2) 111
 Recipient Payment Report HKG page 111
 recipients
 electronic fund transfers 106
 Mandatory Provident Fund membership number 106
 payment report files 110
 processing overview 99
 recipient details 104
 recovering cash advance, termination 150
 regular contributions
 employees contributions 95
 employers mandatory provident fund contributions 94
 Mandatory Provident Fund 93
 regular voluntary contributions
 employees 96
 employer 95

remittance statement, Mandatory Provident Fund (MPF) 97
 rent reimbursement
 calculating 57
 earnings 57
 reports
 Inland Revenue 21, 124, 136, 158
 IR56 data 129
 Mandatory Provident Fund 157
 overview 157
 payslip 159
 recipient payment 158
 retro
 default method 15
 On Conflict Method 15
 processing payments 15
 set up 15
 rolling average
 accumulators 66
 earnings 65
 formulas 67
 variables 67

S

self-employment data, setting up 30
 severance
 earnings 62
 termination 149
 shift allowance
 calculating 53
 earning 53
 sick leave, calculating 151
 source banks, pay entities 101
 Specify Departure Details HKG page 24
 Specify Housing Quarters HKG page 27
 starting sheet numbers, IR56 reports 31
 statutory employees
 annual leave 146
 leave without pay 153
 maternity leave 152
 sick leave 151
 unused annual leave 147
 subsetting, overview 48
 suffixes, overview 11
 supporting elements
 naming convention 8
 type codes 12

T

Tax Reference Number Dtls HKG component
 (GPHK_TAXREF_TBL) 32
 Tax Reference Number Dtls HKG page 33
 templates
 attaching payslip templates to pay groups 43
 creating for payslip 36
 Templates HKG component
 (GPHK_PSLP_SETUP) 36
 termination
 absence entitlements 147
 annual leave in lieu 60
 calculating earnings 60
 Mandatory Provident Fund 87

- of type redundancy 149
- recovering cash advance 150
- severance and long service 62
- thirteenth month pay 63, 148
- unused annual leave 147
- thirteenth month pay
 - calculating 63
 - earnings 58
 - proration 58
 - termination 63, 148
- triggers and segmentation events 16
- typhoon
 - allowance 54
 - calculating 54

V

- variables, rolling average calculation 67
- voluntary permitted period contributions,
 - employer and employee 93

W

- weekly employees, leave without pay 62

