

# **Oracle Utilities Meter Data Management**

Installation Guide

Release 2.0.0

**E18180-01**

August 2010

Copyright © 2000, 2010, Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this software or related documentation is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, the following notice is applicable:

#### U.S. GOVERNMENT RIGHTS

Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, duplication, disclosure, modification, and adaptation shall be subject to the restrictions and license terms set forth in the applicable Government contract, and, to the extent applicable by the terms of the Government contract, the additional rights set forth in FAR 52.227-19, Commercial Computer Software License (December 2007). Oracle America, Inc., 500 Oracle Parkway, Redwood City, CA 94065.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications which may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

This software or hardware and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third party content, products and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third party content, products or services.

---

---

# Contents

<b>Preface</b> .....	<b>i-i</b>
Audience .....	i-i
Related Documents .....	i-i
Conventions .....	i-i
<b>Chapter 1</b>	
<b>Overview</b> .....	<b>1-1</b>
Installation Overview .....	1-2
<b>Chapter 2</b>	
<b>Application Architecture Overview</b> .....	<b>2-1</b>
Application Architecture .....	2-2
Tier 1: Desktop/Client, or Presentation Tier .....	2-2
Tier 2: Web Application / Business Application Server, or Business Logic Tier .....	2-2
Tier 3: Database, or Persistence Tier .....	2-2
<b>Chapter 3</b>	
<b>Supported Platforms and Hardware Requirements</b> .....	<b>3-1</b>
Software and Hardware Considerations .....	3-2
Requirements by Tier .....	3-3
Tier 1, Desktop: Software and Hardware Requirements .....	3-3
Tier 2, Web/Business Application Server: Software and Hardware Requirements .....	3-3
Tier 3, Database Server: Software and Hardware Requirements .....	3-4
Supported Platforms .....	3-5
Operating Systems and Application Servers .....	3-5
Oracle Database Servers .....	3-5
Support for Software Patches and Upgrades .....	3-5
<b>Chapter 4</b>	
<b>Planning the Installation</b> .....	<b>4-1</b>
Installation and Configuration Overview .....	4-2
Before You Install .....	4-3
Installation Checklist .....	4-3
Prerequisite Third-Party Software Overview .....	4-3
Application Framework Installation and Configuration Worksheets .....	4-4
Installation Menu Functionality Overview .....	4-4
Installation Menu Functionality Details .....	4-4
Third Party Software Configuration .....	4-5
Environment Installation Options .....	4-7
Environment Description .....	4-9
Business Application Server Configuration .....	4-10
Web Application Server Configuration .....	4-11
Database Configuration .....	4-14
General Configuration Options .....	4-16
Advanced Menu Options .....	4-17

<b>Chapter 5</b>	
Installing the Database .....	5-1
<b>Chapter 6</b>	
Installing Application Server Prerequisite Software .....	6-1
Oracle Enterprise Linux 5.4 or Red Hat Linux 5.4 Application Server.....	6-2
Supported Application Servers .....	6-2
Web/Application Server Tier.....	6-2
Solaris 10 Application Server.....	6-4
Supported Application Servers .....	6-4
Web/Application Server Tier.....	6-4
Windows 2008 Application Server .....	6-6
Supported Application Servers .....	6-6
Web/Application Server Tier.....	6-6
<b>Chapter 7</b>	
Installing the Application Server Component of Oracle Utilities Application Framework.....	7-1
Installation Overview.....	7-2
Preinstallation Tasks .....	7-3
Hardware and Software Version Prerequisites.....	7-3
Database Installation .....	7-3
Installation Prerequisites .....	7-3
System Architecture Overview .....	7-3
Copying and Decompressing Install Media .....	7-3
Set Permissions for the cistab File in UNIX .....	7-4
Installing Oracle Utilities Application Framework.....	7-5
Brief Description of the Installation Process .....	7-5
Detailed Description of the Installation Process .....	7-5
<b>Chapter 8</b>	
Installing the Application Server Component of Oracle Utilities Meter Data Framework .....	8-1
Preinstallation Tasks .....	8-2
Installing Prerequisite Patches .....	8-2
Copying and Decompressing Install Media .....	8-3
Installing Oracle Utilities Meter Data Framework.....	8-4
Preparing for the Installation .....	8-4
Installing the Application.....	8-4
<b>Chapter 9</b>	
Installing the Application Server Component of Oracle Utilities Meter Data Management .....	9-1
Preinstallation Tasks .....	9-2
Installation Prerequisite.....	9-2
Copying and Decompressing Install Media .....	9-2
Preparing for the Installation .....	9-2
Installing the Application .....	9-3
Post Installation steps:.....	9-3
Installing User Documentation .....	9-4
Installing Stand-Alone Online Help.....	9-4
Operating the Application.....	9-5
<b>Chapter 10</b>	
Additional Tasks .....	10-1
Customizing Configuration Files .....	10-2
Generating the Application Viewer.....	10-3
Building Javadocs Indexes .....	10-4
Configuring the Environment for Batch Processing.....	10-4
Customizing the Logo .....	10-4

## Appendix A

<b>License and Copyright Notices .....</b>	<b>A-1</b>
Third Party Products.....	A-1
Notice concerning usage of ANTLR.....	A-1
Notice concerning usage of Apache Software.....	A-1
Notice concerning usage of ASM.....	A-4
Notice concerning usage of CruiseControl.....	A-5
Notice concerning usage of dom4j .....	A-5
Notice concerning usage of Ehcache.....	A-6
Notices concerning usage of Hibernate and c3p0.....	A-7
Notice concerning usage of International Components for Unicode (ICU4J).....	A-13
Notice concerning usage of fcrypt .....	A-13
Notice concerning usage of Jaxen .....	A-14
Notice concerning usage of JOSSO.....	A-15
Notice concerning usage of libjpeg.....	A-15
Notice concerning usage of libproj4.....	A-16
Notice concerning usage of libtiff.....	A-16
Notice concerning usage of MX4J.....	A-17
Notice concerning usage of PicoContainer .....	A-17
Notice concerning usage of QDox .....	A-18
Notice concerning usage of XStream .....	A-19
Notice concerning usage of Perl.....	A-19
Notice concerning usage of Mime-Base64 Perl Module.....	A-21
Notice concerning usage of Mime-Lite Perl Module .....	A-21
Notice concerning usage of DBD::DB2 Perl Module .....	A-21
Notice concerning usage of DBI Perl Module.....	A-23
Notice concerning usage of JCIP Annotations .....	A-23
Notice concerning usage of YUI Library.....	A-23



---

---

# Preface

This guide describes how to install Oracle Utilities Meter Data Management.

This preface contains these topics:

- **Audience**
- **Related Documents**
- **Conventions**

## Audience

Oracle Utilities Meter Data Management Installation Guide is intended for system administrators installing Oracle Utilities Meter Data Management.

To use this document you should have:

- Experience installing and configuring application servers and other software
- Administrative privileges on the host where you are installing the software

## Related Documents

For more information, see these Oracle documents:

- *Oracle Utilities Meter Data Management Quick Install Guide*
- *Oracle Utilities Meter Data Management Database Administrator's Guide*

## Conventions

The following text conventions are used in this document:

<b>Convention</b>	<b>Meaning</b>
<b>boldface</b>	Boldface type indicates graphical user interface elements associated with an action, or terms defined in text or the glossary.
<i>italic</i>	Italic type indicates book titles, emphasis, or placeholder variables for which you supply particular values.

---

<b>Convention</b>	<b>Meaning</b>
monospace	Monospace type indicates commands within a paragraph, URLs, code in examples, text that appears on the screen, or text that you enter.

---

# Chapter 1

---

## Overview

This chapter provides an overview of the installation of Oracle Utilities Meter Data Management.

## Installation Overview

Installing Oracle Utilities Meter Data Management involves the following steps:

1. Review the different tiers of the application architecture as described in **Chapter 2: Application Architecture Overview**.
2. Understand the hardware requirements for installing the application and the supported platforms for the application and database servers as described in **Chapter 3: Supported Platforms and Hardware Requirements**.

Note: The installation and administration of the database server tier is described in detail in the document *Oracle Utilities Meter Data Management Database Administrator's Guide*.

3. Plan your installation as described in **Chapter 4: Planning the Installation**.
4. Install the database as described in the document *Oracle Utilities Meter Data Management Database Administrator's Guide*.
5. Install all required third-party software as described in **Chapter 6: Installing Application Server Prerequisite Software**. The required software is listed for each supported combination of operating system and application server.
6. Install the framework for the application as described in **Chapter 7: Installing the Application Server Component of Oracle Utilities Application Framework**.
7. Install the meter data framework for the application as described in **Chapter 8: Installing the Application Server Component of Oracle Utilities Meter Data Framework**.
8. Install Oracle Utilities Meter Data Management as described in **Chapter 9: Installing the Application Server Component of Oracle Utilities Meter Data Management**.
9. Follow the installation guidelines described in **Chapter 10: Additional Tasks**.

# Chapter 2

---

## Application Architecture Overview

This section provides an overview of the Oracle Utilities Meter Data Management application architecture.

# Application Architecture

The Oracle Utilities Meter Data Management application is deployed on multiple tiers.

Please see the *Oracle Utilities Meter Data Management Server Administration Guide* for a more detailed description of the application architecture and individual tiers.

## Tier 1: Desktop/Client, or Presentation Tier

This tier is implemented in a browser-based client. Users use a desktop client Web browser to log in to and use the Oracle Utilities Meter Data Management application. Note also that a desktop machine running Microsoft Windows and the Oracle client is required to perform some of the Oracle Utilities Meter Data Management product installation steps.

## Tier 2: Web Application / Business Application Server, or Business Logic Tier

This tier is implemented in a Web application or business application server. The business application component can be installed as part of the Web application server, or as a separate component. Except where explicitly noted, most of the Oracle Utilities Meter Data Management installation documentation assumes that the Web application and business application servers reside together.

## Tier 3: Database, or Persistence Tier

This tier is implemented in a database server. The database server stores data maintained by the Oracle Utilities Meter Data Management application. More specifically, the database tier contains the data server files and database executables that physically store the tables, indexes, and other database objects for your system.

# Chapter 3

---

## Supported Platforms and Hardware Requirements

This section gives an overview of the tiers on which the product is implemented, and shows each of the operating system/server combinations that the product is certified for. It includes:

- **Software and Hardware Considerations**
- **Requirements by Tier**
- **Supported Platforms**
- **Support for Software Patches and Upgrades**

## Software and Hardware Considerations

There are many factors that can influence software and hardware decisions. For example, your system may have to satisfy specific performance, availability, or scalability requirements, or to support running in a language other than English. These business requirements, together with the chosen system architecture, should be used in initial software and hardware planning.

Some of the questions that you should answer before beginning the installation include:

- On which hardware platform and operating system will Oracle Utilities Meter Data Management be deployed?
- On which Web server product will Oracle Utilities Meter Data Management deploy?
- On which database product will Oracle Utilities Meter Data Management deploy?
- Do you plan to deploy multiple Oracle Utilities Meter Data Management instances on the same physical server?
- How do you plan to deploy Oracle Utilities Meter Data Management?
  - Web/application/database on the same physical server
  - Web/application on one server and database on separate server
  - Each component on its own server

For detailed descriptions of various deployment architecture choices that may aid in planning, please see the document *Oracle Utilities Application Framework Architecture Guidelines*, available on My Oracle Support (Article ID 807068.1).

The final hardware and software decisions must comply with the specific requirements of Oracle Utilities Meter Data Management, as described in the rest of this chapter.

## Requirements by Tier

The application is deployed on multiple Tiers:

- Tier 1, Desktop
- Tier 2, Web/Business Application Server
- Tier 3, Database Server

### Tier 1, Desktop: Software and Hardware Requirements

Configuration	Processor	Memory (RAM)	Monitor Display
Minimum	Pentium IV - 2.0 GHz	1024 MB	1024X768** 16-bit Color
Recommended*	Pentium IV - 3.0+ GHz, Or any Core 2 Duo Or any Athlon X2	2048 MB	1280X1024* 32-bit Color

\* The Recommended configuration will support better performance of the client.

\*\* To reduce the amount of scrolling required for pages that are longer than 768 or 1024 pixels, consider placing a monitor into vertical position (with narrow side on the bottom).

### Web Browser Requirements

The following Operating System / Web Browser software is supported:

- Windows XP SP3 or higher with Internet Explorer 7.x or 8.x
- Windows 7 with Internet Explorer 7.x or 8.x

### Tier 2, Web/Business Application Server: Software and Hardware Requirements

Please consult the **Supported Platforms** on page 3-5 to determine which Web application servers can be used with the operating system that will be hosting this tier.

The recommendations that follow are based on a standard installation with both the application and business servers on the same machine and the system running with the default values. The minimum resource requirements exclude third-party software installation requirements. Refer to the third-party vendors for specific requirements. The following sizing excludes the Oracle database server installation.

### Memory Requirements

For each application server environment a minimum of 4 GB of real memory is required, plus 6 GB of swap space.

## Disk Space Requirements

The approximate disk space requirements in a standard installation are as follows:

Location	Size	Usage
\$SPLEBASE	5 GB minimum	This location is where the application and Framework get installed. Startup, shutdown and other online log files are stored here. The size and space that is used should be monitored because various debugging options can significantly affect the size of log files.
\$SPLAPP	2 GB minimum	This location is used for storing batch log files and output from batch jobs. The size of this space should be influenced by which batches are run and how often, and the amount of debugging information that is collected.
Location of the application Web work files on the Web servers	1.5 GB minimum	This location is used by the various Web server vendors to expand the application. It should be considered when installing these products. Refer to the individual Web server documentation to determine the location of the temporary files.
Installation temporary area	4 GB	The application gets installed from this location. You need enough space to uncompress the files and install the application.
Oracle data area	4 GB minimum	This location is where the Oracle database data files are stored. The size of this space should be based on the requirements of the production environment. For an initial or demo database install 4 GB should be sufficient.

## Tier 3, Database Server: Software and Hardware Requirements

See the section **Supported Platforms** on page 3-5 for supported database servers.

## Supported Platforms

The installation has been tested and certified to operate on many operating system, application server, and database server combinations. For the software requirements for each of these combinations, see **Chapter 6: Installing Application Server Prerequisite Software** for more information.

### Operating Systems and Application Servers

The following table details the operating system and application server combinations on which Oracle Utilities Meter Data Management version 2.0.0 has been tested and certified.

Browser	Operating System (Client)	Operating System (Server)	Chipset	Application Server	Database
IE 7.x	Windows XP SP3	Oracle Enterprise Linux 5.4 (64-bit)	x86_64	WebLogic 10.3.3	Oracle 11.2.0.1
		Red Hat Enterprise Linux 5.4 (64-bit)			
IE 8.x	Windows 7	Sun Solaris 10 Update 8 (64-bit)	SPARC	WebLogic 10.3.3	Oracle 11.2.0.1
		Windows 2008 Server SP2	x86_64	WebLogic 10.3.3	Oracle 11.2.0.1

### Oracle Database Servers

Oracle Utilities Meter Data Management version 2.0.0 is supported with Oracle Database Server 11.2.0.1 on all of the operating systems listed above.

The Oracle 11.2.0.1 client is required for this version of the database server.

The following Oracle Database Server Editions are supported:

- Oracle Database Server Standard Edition
- Oracle Database Server Enterprise Edition

### Support for Software Patches and Upgrades

Due to the ongoing nature of software improvement, vendors will issue patches and service packs for the operating systems, application servers and database servers on top of specific versions that Oracle Utilities Meter Data Management has been tested with.

If it is necessary to apply an upgrade, please do that in a test environment prior to updating the Oracle Utilities Meter Data Management production environment.

The only exception from this rule is Hibernate software. For this the exact version mentioned in this guide must be installed. Please always check with Oracle Utilities Meter Data Management support prior to installing Hibernate updates.

Always contact Oracle Utilities Meter Data Management support prior to applying vendor updates that do not guarantee backward compatibility.



# Chapter 4

---


## Planning the Installation

This chapter provides information for planning an Oracle Utilities Meter Data Management installation, including:

- **Installation and Configuration Overview**
- **Before You Install**
- **Installation Checklist**
- **Prerequisite Third-Party Software Overview**
- **Application Framework Installation and Configuration Worksheets**

# Installation and Configuration Overview

The following diagram provides an overview of the steps that need to be taken to install and configure Oracle Utilities Meter Data Management:



---

## Before You Install

Refer to My Oracle Support for up-to-date additional information on Oracle Utilities Meter Data Management installation.

## Installation Checklist

The following checklist will help guide you through the installation process of the application tier. The details for each step are presented in subsequent chapters.

1. Create Group/User ID.
2. Install prerequisite software (see **Prerequisite Third-Party Software Overview** on page 4-3 for more information).
  - Oracle client 11.2.0.1 (for connecting to Oracle database)
  - Java 6
  - Hibernate 3.3.2
3. Install Web Server.
  - Oracle WebLogic 10.3.3
4. Verify that all software installed.
5. Set up environment variables.
6. Install Oracle Utilities Application Framework.
7. Install Oracle Utilities Application Framework prerequisite single fixes.
8. Install Oracle Utilities Meter Data Framework.
9. Install Oracle Utilities Meter Data Management.
10. Deploy Oracle Utilities Meter Data Management application.
11. Post installation tasks.

## Prerequisite Third-Party Software Overview

For complete details about installing and configuring the prerequisite third-party software for your specific platform, see **Chapter 6: Installing Application Server Prerequisite Software**.

# Application Framework Installation and Configuration Worksheets

During the installation and configuration of the application you will need to provide a variety of system values. These worksheets will assist you in providing that information. They should be completed before installing the application framework, as described in **Chapter 7: Installing the Application Server Component of Oracle Utilities Application Framework**. No Customer Install Value fields should be left blank.

Note: Some web application server information will not be available until the software installation steps have been completed as described in **Chapter 6: Installing Application Server Prerequisite Software**.

## Installation Menu Functionality Overview

The main configuration menu is structured so that related variables and/or options are grouped together and are associated by a menu item number. To access a particular group of variables and options, enter the menu item number associated with that group. Each option within that group is displayed in turn on the screen, along with a prompt so that you can type the desired value for the option, if it is not the same as the default or current value.

When performing the initial installation you need to go through all menu options. The menu options may have a default value, a list of valid values and a validation check.

On each option prompt you can keep the current value by simply leaving the input line empty. In order to erase a variable value you need to enter one dot (“.”). The leading spaces will be trimmed out on each values entered.

When all options are set, type <P> at the main menu prompt option. This will save the option values selected throughout the configuration.

During this processing the global variables are validated and the configuration file <SPLEBASE>/etc/ENVIRON.INI is created or updated. This file contains all the variables inputted and calculated. These are needed by the next part of the installation process.

To exit the configuration utility without saving any of the values entered, type <X> and 'Enter'

## Installation Menu Functionality Details

The Environment Installation Utility requires that Oracle Client Home is set in the path for the user performing the installation.

Prior to running the installation utility you will need to review the supported platforms document to ensure you have all of the Third Party software installed.

In this menu if the variables are set prior to execution, that value will be used by the installation utility when performing the installation.

When the installation has been completed successfully, the values will be written to an ENVIRON.INI file. When splenviron.sh / cmd is executed, it will read from the ENVIRON.INI file to set the environment variables.

In the worksheets there are two different types of values given:

- Default values are the values that will be defaulted when running the installation utility.
- Example Values show examples of values that you can be used for a default installation.

Passwords are entered in silent mode and are encrypted as they are entered.

Install the Oracle Client software specified in **Supported Platforms** on page 3-5 prior to running any of the installation utilities.

The following prompt will appear when executing the installation utility:

Enter Oracle Client Home Directory (<ENTER> quit):

**Note:** If the environmental variable ORACLE\_CLIENT\_HOME is set, the install script will validate the variable. If it passes the validation you will not be prompted for it. This is needed in order to run Perl installation utilities.

## Third Party Software Configuration

```

*****
* Environment Installation Options *
*****
1. Third Party Software Configuration
   Oracle Client Home Directory:
   Web Java Home Directory:
   Child JVM Home Directory:
   COBOL Home Directory:
   Hibernate JAR Directory:
   Database Home Directory:
   Web Application Server Home Directory:
   ADF Home Directory:

```

Menu Option	Name Used In Documentation	Usage	Customer Install Value
Oracle Client Home Directory	ORACLE_CLIENT_HOME	The home directory of the Oracle Client. The application will use the Perl included under this Oracle Client.  Example Location: /oracle/client/product/11.2.0.1	
Web Java Home Directory	JAVA_HOME	Java home that will be used by the Web application server.  Example Location: /ouaf/java/jdk1.6.0_18	
* Child JVM Home Directory	CHILD_JVM_JAVA_HOME	Java home that will be used by the child java process that handles COBOL related requests.  Example Location: /ouaf/java/jdk1.6.0_18  Note: This menu option is not applicable to Oracle Utilities Meter Data Management.	

Menu Option	Name Used In Documentation	Usage	Customer Install Value
* COBOL Home Directory	COBDIR	COBOL installation location directory.  Example Location: /opt/SPLcobAS51WP4  Note: This menu option is not applicable to Oracle Utilities Meter Data Management.	
Hibernate JAR Directory	HIBERNATE_JAR_DIRECTORY	Location on the disk where the hibernate3.jar is installed.	
Database Home Directory	DATABASE_HOME	Location on the disk where database client is installed for your particular installation.  Example Location for Oracle Database: /oracle/client/product/11.2.0.1	
Web Application Server Home Directory	WEB_SERVER_HOME	Location on the disk where the application server is installed.  Example Location: WebLogic: /ouaf/middleware/wlserver_10.3	
* ADF Home Directory	ADF_HOME	Location on the disk where ADF is installed.  Example Location: /ouaf/jdev11_1_1_2  Note: This menu option is not applicable to Oracle Utilities Meter Data Management.	

\* Denotes optional Menu Options and Variables.

## Environment Installation Options

### 50. Environment Installation Options

Environment Mount Point:

Log Files Mount Point:

Environment Name:

Database Type:

Web Application Server Type:

Install Only Web Component: false

Menu Option	Name Used In Documentation	Usage	Customer Install Value
Environment Mount Point	<SPLDIR>	<p>The mount point into which the application is installed. For example: /ouaf for UNIX and C:\ouaf for Windows.</p> <p>This mount point MUST exist and the Oracle Utilities Application Framework administrator user id MUST be able to write to this directory. (This is the user id that is created specifically to administer the Oracle Utilities Application Framework environments; the default is cissys). The installation sets permissions on all subdirectories installed under this directory.</p> <p>See &lt;SPLENVIRON&gt; below for more information on how this mount point is used.</p>	
Log File Mount Point	<SPLDIROUT>	<p>A mount point that will contain any application output or application logs. Default value is /ouaf/sploutput for UNIX installation or C:\ouaf\sploutput for Windows.</p> <p>Before you start the install, ensure that this mount point exists and that the Oracle Utilities Application Framework administrator user id (cissys) can write to this directory. For each environment initialized, the application logs will be written to the directory &lt;SPLDIROUT&gt;/&lt;SPLENVIRON&gt;</p> <p>Note: Later in the installation, the splenvron.sh ( splenvron.cmd ) script will set the \$SPOUTPUT (%SPOUTPUT%) environment variable to point to:&lt;SPLDIROUT&gt;/&lt;SPLENVIRON&gt;</p>	

Menu Option	Name Used In Documentation	Usage	Customer Install Value
Environment Name	<SPLENVIRON>	<p>A descriptive name to be used as both a directory name under the mount point &lt;SPLDIR&gt; and an environment descriptor. This value typically identifies the purpose of the environment. For example, DEV01 or CONV.</p> <p>On installation a directory &lt;SPLDIR&gt;/&lt;SPLENVIRON&gt; is created, under which the Oracle Utilities Application Framework and Oracle Utilities Application software resides.</p> <p>When multiple environments are set up on the machine you will typically have directories such as: /ouaf/DEV01/.... /ouaf/CONV/....</p> <p>Each of these contains a complete version of the Oracle Utilities Application Framework and Oracle Utilities Meter Data Management.</p> <p>Note: Later in the installation process, the splenviron.sh (splenviron.cmd) script will set \$SPLEBASE (%SPLEBASE%) environment variable to point to &lt;SPLDIR&gt;/&lt;SPLENVIRON&gt;</p>	
Database Type	<CMPDB>	<p>Type of a database to connect an environment to.</p> <p>Valid Values: oracle: Oracle</p> <p>Note: Not all Database Types are supported on all platforms; refer to the Supported Platforms section for details.</p>	
Web Application Server Type	<SPLWAS>	<p>A Web Application Server for the environment to be used. The following value must be selected:</p> <p>Valid Values: WLS: WebLogic</p> <p>Note: Not all Web Application servers are supported on all platforms; refer to Supported Platforms section for details.</p>	
Install Web Only Component		For future releases of the Oracle Utilities Application Framework installations.	

# Environment Description

- 1. Environment Description  
Environment Description:

<b>Menu Option</b>	<b>Name used in this Documentation</b>	<b>Usage</b>	<b>Customer Install Value</b>
Environment Description	DESC	This is a free form text field to describe the use of the environment.	

## Business Application Server Configuration

=====

2. Business Application Server Configuration

```

Business Server Host:                <machine_name>
WebLogic Server Name:                myserver
Business Server Application Name:    SPLService
MPL Admin Port Number:
MPL Automatic startup:                false
    
```

=====

**Note:** The WebLogic parameters above and in the worksheet are for a WebLogic installation. The parameters for your installation will include your type of application server.

Menu Option	Name used in this Documentation	Usage	Customer Install Value
Business Server Host	BSN_WLHOST	The host name on which business application server resides.  Default Value: <current server name>	
WebLogic Server Name	BSN_WLS_SVRNAME	The name of the WebLogic server where the business application resides.  Default value: myserver	
Business Server Application Name	BSN_APP	The name of the business application server.  Default: SPLService	
MPL Admin Port number	MPLADMINPORT	The port number for the Multi Purpose Listener (MPL) Admin Server.  Example Value: 6502  Note: MPL is deprecated and is retained for backward compatibility.	
MPL Automatic Startup	MPLSTART	Automatically starts the MPL Listener whenever environment starts. Default value: false  Note: MPL has been deprecated and is retained for backward compatibility.	

## Web Application Server Configuration

### 3. Web Application Server Configuration

```

Web Server Host: <machine_name>
Web Server Port Number:
WebLogic SSL Port Number:
Web Context Root: ouaf
WebLogic JNDI User ID:
WebLogic JNDI Password:
WebLogic Admin System User ID:
WebLogic Admin System Password:
WebLogic Server Name: myserver
Web Server Application Name: SPLWeb
Application Admin User ID:
Application Admin Password:
Expanded Directories: false
Application Viewer Module: true

```

=====

**Note:** The WebLogic parameters above and in the worksheet are for a WebLogic installation. The parameters for your installation will include your type of application server.

Menu Option	Name used in this Documentation	Usage	Customer Install Value
Web Server Host	WEB_WLHOST	The host name on which the Web application Server resides.  Default Value: <current server name>	
Web Server Port Number	WEB_WLPORT	A unique port number within the system that will be assigned to the HTTP port. This is the port number that is used as a part of the client URL request to connect to the host.  Example Value: 6500	
WebLogic SSL Port Number:	WEB_WLSSPORT	The port number assigned to WebLogic Secure Sockets connection. This is the port number that is used for Secure Sockets connecting to the WebLogic server. The Secure Sockets implementation is disabled in the default configuration.  Example Value: 6501	
Web Context Root	WEB_CONTEXT_ROOT	A context root name that allows customers to run multiple instances of Web application on the same server.  Default Value: ouaf	

Menu Option	Name used in this Documentation	Usage	Customer Install Value
WebLogic JNDI User ID	WEB_WLSYSUSER	The user ID the application uses to connect to the EJB component through JNDI. This is the EJB container User ID.  Note: A new installation requires use of the user ID of system.	
WebLogic JNDI Password	WEB_WLSYSPASS	The password the application uses to connect to the EJB component through JNDI  Note: A new installation requires the use of the password ouafadmin. This value will be saved in encrypted format	
WebLogic Server User ID	WLS_WEB_WLSYSUSER	User ID to login to WebLogic console and to administer WebLogic. The WebLogic startup and stop script use this user ID.  Note: A new installation requires use of the user ID of the system. This value will be saved in encrypted format.	
WebLogic Server Password	WLS_WEB_WLSYSPASS	On the configuration step of install process you can change this password to a different value. This should only be done if you have changed the password on an existing system following the Oracle WebLogic instructions. The WebLogic startup and stop script use this password.  Note: A new installation requires the use of the password ouafadmin. This value will be saved in encrypted format.	
WebLogic Server Name	WEB_WLS_SVRNAME	The name of the WebLogic server where the Web application resides.  Default Value: myserver	
Web Server Application Name	WEB_APP	The name of the Web application server.  Default Value: SPLWeb	
Application Admin User ID	WEB_SPLUSER	This is the default user ID to login to the application through the browser.  Example Value: SYSUSER  Note: This value is also used in communication within the XAI application.	

Menu Option	Name used in this Documentation	Usage	Customer Install Value
Application Admin Userid Password	WEB_SPLPASS	<p>This is the password of the application admin user.</p> <p>Example Value: sysuser00</p> <p>Note: This value will be saved in encrypted format</p>	
Expanded Directories	WEB_ISEXPANDED	<p>When the value is “true” the Web application will be deployed in exploded directory format (no WAR files).</p> <p>When the value is “false”, the web application will be deployed in ear file format.</p> <p>Default Value: false</p>	
Application Viewer Module	WEB_ISAPPVIEWER	<p>When the value is “true” the application viewer will be deployed to the Web server. When the value is “false”, the application viewer will not be deployed to the Web Server.</p> <p>Note: With either value the application viewer module will still be managed by the upgrade process.</p> <p>Default Value: true</p>	

## Database Configuration

### 4. Database Configuration

```

JDBC Name:
MPL Database User ID:
MPL Database Password:
XAI Database User ID:
XAI Database Password:
Batch Database User ID:
Batch Database Password:
JDBC Database User ID:
JDBC Database Password:
Database Name:
Database Server:
Database Port:
ONS Server Configuration:
Database Override Connection String:
Oracle Client Character Set NLS_LANG:      AMERICAN_AMERICA.UTF8

```

=====

Menu Option	Name Used in this Documentation	Usage	Customer Install Value
JDBC Name	JDBC_NAME	The connection pool name to use for the JDBC driver to create physical database connections. The connection pool contains a group of JDBC connections that are created when starting up WebLogic Server or when deploying the connection pool to a target server.  Example Value: [YOUR_NAME]-jdbc	
MPL Database User ID	MPL_DBUSER	The database user ID that has been configured on the database for the MPL server connection.	
MPL Database Password	MPL_DBPASS	The database password that has been configured on the database for the MPL server connection.  Note: This value will be saved in encrypted format.	
XAI Database User ID	XAI_DBUSER	The database user ID that has been configured on the database for the XAI server connection.	
XAI Database Password	XAI_DBPASS	The database password that has been configured on the database for the XAI server connection.  Note: This value will be saved in encrypted format.	

<b>Menu Option</b>	<b>Name Used in this Documentation</b>	<b>Usage</b>	<b>Customer Install Value</b>
Batch Database User ID	DBUSER	The database user ID that has been configured on the database for the batch connection.	
Batch Database Password	DBPASS	The database password that has been configured on the database for the batch connection.  Note: This value will be saved in encrypted format.	
JDBC Database User ID		The database user ID that has been configured on the database for the WebLogic JDBC connection.	
JDBC Database Password		The database password that has been configured on the database for the WebLogic JDBC server connection.  Note: This value will be saved in encrypted format.	
Database Name	DBNAME	The name of the database instance that the application will be connecting to.	
Database Server	DBSERVER	Host name of the server where database resides.	
Database Port	DBPORT	Database port number on the database server used for connecting to the database	
ONS Server Configuration	ONSCONFIG	ONS Server Configuration is required for Oracle RAC FCF.  This option is for future use.	
Database Override Connection String	DB_OVERRIDE_CONNECTION	This connection string can be used to override the database information entered above for RAC installation.  Set this string to override the standard database connection string, as entered above.	
Oracle Client Character Set NLS_LANG	NLS_LANG	The Oracle Database Character Set.  Select the Language and Territory that are in use in your country.  Default Value: AMERICAN_AMERICA.UTF8	

## General Configuration Options

### 5. General Configuration Options

Batch RMI Port:  
 Batch Mode: CLUSTERED  
 Coherence Cluster Name:  
 Coherence Cluster Address:  
 Coherence Cluster PORT:  
 Coherence Cluster Mode: dev

Menu Option	Name used in this Documentation	Usage	Customer Install Value
Batch RMI Port	BATCH_RMI_PORT	Unique port used by the Batch RMI	
Batch Mode	BATCH_MODE	Valid Values: CLUSTERED or DISTRIBUTED  Default Value: CLUSTERED Note: CLUSTERED is currently the only supported mode for production environments.	
Coherence Cluster Name	COHERENCE_CLUSTER_NAME	Unique name for the batch CLUSTER	
Coherence Cluster Address	COHERENCE_CLUSTER_ADDRESS	Unique multicast address.	
Coherence Cluster PORT	COHERENCE_CLUSTER_PORT	Unique port for the batch CLUSTER	
Coherence Cluster Mode	COHERENCE_CLUSTER_MODE	Valid Values: dev (Development) prod (Production)  Default Value: dev	

Note: See the Oracle Utilities Meter Data Management *Batch Server Administration Guide* for additional details on this configuration.

## Advanced Menu Options

The advanced menu options are not available during installation. These options can be accessed after installation using the following commands:

### Unix:

```
$SPLEBASE/bin/configureEnv.sh -a
```

### Windows

```
%SPLEBASE%\bin\configureEnv.cmd -a
```

## Advanced Environment Miscellaneous Configuration

```
50. Advanced Environment Miscellaneous Configuration
    This is a development environment:                false
    Preload All Pages on Startup:                      false
    Maximum Age of a Cache Entry for Text:             28800
    Maximum Age of a Cache Entry for Images:           28800
    JSP Recompile Interval (s):                       43200
    Authentication Login Page Type:                   FORM
    Online JVM Batch Server Enabled:                   false
    Online JVM Batch Number of Threads:                5
    Online JVM Batch Scheduler Daemon Enabled:         false
    JMX Enablement System User ID:
    JMX Enablement System Password:
    RMI Port number for JMX Business:
    RMI Port number for JMX Web:
    RAC Initial Limit:                                0
    RAC Minimum Limit:                                0
    RAC Maximum Limit:                                0
    GIS Service Running on the same Web Server:       true
    GIS Service URL:
    GIS WebLogic System User ID:
    GIS WebLogic System Password:
    DOC1 Host Directory:
```

Menu Option	Name used in this Documentation	Usage	Customer Value Install
This is a development environment	WEB_ISDEVELOPMENT	<p>If the value is “true”, the Web application may be used for application development, which will trigger certain generation processes. If the value is “false” the environment will be used as a runtime environment.</p> <p>When you choose “true” (development environment) the startup preload pages will be disabled, and the application security will be less strict. This value also controls the amount of logging information written to the application log files.</p> <p>Valid Values: true, false</p> <p>Default Value: false</p>	

Menu Option	Name used in this Documentation	Usage	Customer Value Install
Preload All Pages on Startup	WEB_PRELOADALL	This controls if the pages should be pre-loaded during the startup of the application or not.  Valid Values: true, false  Default Value: false	
Maximum Age of a Cache Entry for Text	WEB_MAXAGE	Default Value: 28800	
Maximum Age of a Cache Entry for Images	WEB_MAXAGEI	Default Value: 28800	
JSP Recompile Interval (s)	WEB_wlpageCheckSeconds	Default Value: 43200	
Authentication Login Page Type	WEB_WLAUTHMETHOD	Specifies which authentication mode should be used. To switch off OUAF Login Page enter: BASIC  Valid Values: FORM, BASIC  Default Value: FORM	
Online JVM Batch Server Enabled	BATCHENABLED	When starting a web application server JVM, this property can be set to “true” to allow the on-line application server to also act as a batch worker in the grid.  Default Value: false  Note: This functionality should only be used in low volume environments.	
Online JVM Batch Number of Threads	BATCHTHREADS	The maximum number of batch processing threads to be executed within a worker JVM when no explicit Distributed Thread Pool is specified. The “DEFAULT” distributed thread pool is used by the batch-scheduling daemon when it initiates processing on batch jobs (typically added via the online system) where no threadpool is specified.  Default Value: 5  Note: This will be only used and activated when BATCHENABLED is set to true.	

Menu Option	Name used in this Documentation	Usage	Customer Value Install
Online JVM Batch Scheduler Daemon Enabled	BATCHDAEMON	In a distributed batch environment, this property can be set to “true” to allow a worker JVM to host the batch scheduling daemon. The daemon accepts online batch submissions requests and automatically submits the work for them.  Valid Values: true, false  Default Value: false  Note: This will be only used and activated when BATCHEENABLED is set to true.	
JMX Enablement System User ID	BSN_JMX_SYSUSER	Example Value: user	
JMX Enablement System Password	BSN_JMX_SYSPASS	Example Value: admin	
RMI Port number for JMX Business	BSN_JMX_RMI_PORT_PERFORMACE	This needs to be set to an available port number on the machine	
RMI Port number for JMX Web	WEB_JMX_RMI_PORT_PERFORMACE	This needs to be an available port number for the environment running on the machine	
RAC Initial Limit	RAC_INITIALLIMIT	Required for Oracle RAC FCF. This is for future use.  Default Value: 0	
RAC Minimum Limit	RAC_MINLIMIT	Required for Oracle FCF  Default Value: 0	
RAC Maximum Limit	RAC_MAXLIMIT	Required for Oracle FCF  Default Value: 0	
GIS Service Running on the same Web Server	GIS	Geographical information (GEOCODING) - GIS Service running on the same Web application server  Valid Values: true, false	
GIS Service URL	GIS_URL	This is the URL of the external Web server.  Note: This value will be only be used when GIS is set to true.	
GIS WebLogic System User ID	GIS_WLSYSUSER	GIS WebLogic System User ID  Note: This value will be only be used when GIS is set to true.	

Menu Option	Name used in this Documentation	Usage	Customer Value Install
GIS WebLogic System Password	GIS_WLSYSPASS	GIS WebLogic System Password.  Note: This value will be only be used when GIS is set to true.	
DOC1 Host Directory	DOC1HOSTDIR	The location of the DOC1 installation. This value is optional	

## Advanced Environment Memory Configuration

```

51. Advanced Environment Memory Configuration
    JVM Child Memory Allocation:                    512
    JVM Child Additional Options:
    Web Application Java Initial Heap Size:         1024
    Web Application Java Max Heap Size:             1024
    Web Application Java Max Perm Size:             500
    Web Application Additional Options:
    Ant Min Heap Size:                              200
    Ant Max Heap Size:                              800
    Ant Additional Options:
    Thread Pool Worker Java Min Heap Size:         512
    Thread Pool Worker Java Max Heap Size:         1024
    Thread Pool Worker Java Max Perm Size:         768
    Thread Pool Worker Additional Options:
    Additional Runtime Classpath:
    Release Cobol Thread Memory Options:
    -Dspl.runtime.cobol.remote.releaseThreadMemoryAfterEachCall=...

```

Usage	Name used in this Documentation	Usage	Customer Install Value
JVM Child Memory Allocation	JVMMEMORYARG	Heap size for the JVM Child.  Default Value: 512	
JVM Child Additional Options	JVM_ADDITIONAL_OPT	Additional JVM options that are passed to the Child JVM.	
Web Application Java Initial Heap Size	WEB_MEMORY_OPT_MIN	Initial heap size for the application server.  Default Value: 1024	
Web Application Java Max Heap Size	WEB_MEMORY_OPT_MAX	Maximum heap size for the application server.  Default Value: 1024	

Usage	Name used in this Documentation	Usage	Customer Install Value
Web Application Java Max Perm Size	WEB_MEMORY_OPT_MAXPERMSIZE	Maximum Perm Size for the application server.  Default Value: 500MB (Linux, Solaris) 300MB (Windows, HP-UX)	
Web Application Additional Options	WEB_ADDITIONAL_OPT	Additional options that will be passed in to the web application server JVM.  Optional Entry.	
Ant Min Heap Size	ANT_OPT_MIN	Minimum Heap Size passed to ANT JVM.  Default Value: 200	
Ant Max Heap Size	ANT_OPT_MAX	Maximum Heap Size passed to ANT JVM.  Default Value: 800	
Ant Additional Options	ANT_ADDITIONAL_OPT	Additional options that are passed into the ANT JVM.	
Thread Pool Worker Java Min Heap Size	BATCH_MEMORY_OPT_MIN	Minimum heap size passed to the Thread Pool Worker.  Default Value: 512	
Thread Pool Worker Java Max Heap Size	BATCH_MEMORY_OPT_MAX	Maximum heap size passed to the Thread Pool Worker.  Default Value: 1024	
Thread Pool Worker Java Max Perm Size	BATCH_MEMORY_OPT_MAXPERMSIZE	Maximum permanent heap size passed to the Thread Pool Worker.  Default Value: 768	
Thread Pool Worker Additional Options	BATCH_MEMORY_ADDITIONAL_OPT	Additional Memory Options passed into the Thread Pool Worker. This is an optional free form field.	
Additional Runtime Classpath	ADDITIONAL_RUNTIME_CLASSPATH	Additional Classpath Options passed in when starting the WebLogic JVM  This is an optional free form field.	

<b>Usage</b>	<b>Name used in this Documentation</b>	<b>Usage</b>	<b>Customer Install Value</b>
Release Cobol Thread Memory Options	REL_CBL_THREAD_MEM	<p>Allow for child JVMs to be optionally configured to release thread-bound memory when each thread is returned to its thread pool. This will increase the number of memory allocations and memory free calls performed by the Microfocus runtime. It will also lower the amount of C-heap memory consumed by child JVMs.</p> <p>Valid Values: true, false</p> <p>Default Value: false</p>	

# Chapter 5

---

## Installing the Database

Please review Chapter 1 of this guide and then follow the steps for installing the database as described in the *Oracle Utilities Meter Data Management Database Administrator's Guide*.



# Chapter 6

---

## Installing Application Server Prerequisite Software

This chapter describes the software that needs to be installed for each of the supported operating system and application server combinations. The sections for this chapter are:

- **Oracle Enterprise Linux 5.4 or Red Hat Linux 5.4 Application Server**
- **Solaris 10 Application Server**
- **Windows 2008 Application Server**

# Oracle Enterprise Linux 5.4 or Red Hat Linux 5.4 Application Server

This section describes the software requirements for operating the application using the Oracle Enterprise Linux or Red Hat Linux application server.

## Supported Application Servers

Operating System	Chipsets	Application Server
<b>Oracle WebLogic 11gR1 (10.3.3)</b>		
Oracle Enterprise Linux 5.4 (64-bit) Red Hat Enterprise Linux 5.4 (64-bit)	x86_64	64-bit version

## Web/Application Server Tier

### Oracle Enterprise Linux 5.4 or Red Hat Enterprise Linux 5.4 Operating System Running on x86\_64 64-bit Architecture

#### UNIX Administrator Userid

The following user groups and accounts have to be created to install and administer the application:

Description	Default Value	Customer Defined Value
Oracle Utilities Meter Data Management Administrator User ID	cissys	
Oracle Utilities Meter Data Management User Group	cisusr	

Note: It is recommended that you change the default values for security reasons.

Throughout this document the administrator user id is often referred to as the "cissys" user id. You should substitute that with the customer defined user id when not using the default value. After the initial install, the software should always be managed using that user id.

By default, the cissys userid is the only one given access to the files installed.

1. Create a group called cisusr (user group)
2. Create a user called cissys. Primary group cisusr. Set the primary shell for the cissys user to Korn Shell.

The shell scripts use the ">" to overwrite shell functionality. Your operating system may be configured to not allow this functionality by default in the users shell.

To avoid file access permission problems when executing scripts, consider placing the following command into cissys profile script:

```
set +o noclobber
```

### Oracle 11.2.0.1 Client

The Java JDBC drivers must be installed as part of the client install.

Ensure that the userid cissys has been setup to be able to communicate with the Oracle database. Use the command:

```
tnsping $ORACLE_SID
```

Use the cissys account to install the Oracle Client.

The Oracle 11.2.0.1 Client is required regardless of the version of the database server.

### Sun Java Development Kit Version 6.0 Update 18

At time of release, Solaris Java packages could be obtained from:

<http://java.sun.com/products/archive/index.html>

The Oracle WebLogic Server requires the 64-bit version. The main prerequisite for the Web server is the version of java mentioned above.

For the userid cissys, ensure that the environment variable JAVA\_HOME is setup, and that java\_home/bin and java\_home/lib can be found in cissys' PATH variable.

### Hibernate 3.3.2

Hibernate must be installed prior to the installation of Oracle Utilities Meter Data Management.

Please download the file hibernate-3.3.2.ga.zip from the following link:

<http://prdownloads.sourceforge.net/hibernate/>

or from the following link:

[http://sourceforge.net/project/showfiles.php?group\\_id=40712&package\\_id=127784](http://sourceforge.net/project/showfiles.php?group_id=40712&package_id=127784)

It is very important that you download the exact version, as the product has only been certified with this exact release.

You will need to create a permanent directory to place one of the files from hibernate-3.3.2.ga.zip. (e.g. \opt\hibernate3.3.2).

Extract the file hibernate3.jar from hibernate-3.3.2.ga.zip.

### Oracle WebLogic 11gR1 (10.3.3) 64-bit

Oracle WebLogic software can be downloaded from the Oracle web site. This application server will run as a 64-bit application. This application server will run as a 64-bit application.

- Download and install 64-bit Java (as documented above) before installing WebLogic.
- Download and install WebLogic Server 11gR1 (10.3.3).

# Solaris 10 Application Server

This section describes the software requirements for operating the application using the Sun Solaris 10 application server.

## Supported Application Servers

Operating System	Chipsets	Application Server
<b>Oracle WebLogic 11gR1 (10.3.3)</b>		
Solaris 10 Update 8 (64-bit)	SPARC	64-bit version

## Web/Application Server Tier

### Solaris 10 Operating System Running on SPARC-based 64-bit Architecture

#### UNIX Administrator Userid

The following user groups and accounts have to be created to install and administer the application:

Description	Default Value	Customer Defined Value
Oracle Utilities Meter Data Management Administrator User ID	cissys	
Oracle Utilities Meter Data Management User Group	cisusr	

Note: It is recommended that you change the default values for security reasons.

Throughout this document the administrator user id is often referred to as the "cissys" user id. You should substitute that with the customer defined user id when not using the default value. After the initial install, the software should always be managed using that user id.

By default, the cissys userid is the only one given access to the files installed.

1. Create a group called cisusr (user group)
2. Create a user called cissys. Primary group cisusr. Set the primary shell for the cissys user to Korn Shell.

The shell scripts use the ">" to overwrite shell functionality. Your operating system may be configured to not allow this functionality by default in the users shell.

To avoid file access permission problems when executing scripts, consider placing the following command into cissys profile script:

```
set +o noclobber
```

#### Oracle 11.2.0.1 Client

The Java JDBC drivers must be installed as part of the client install.

Ensure that the userid cissys has been setup to be able to communicate with the Oracle database.  
Use the command:

```
tnsping $ORACLE_SID
```

Use the cissys account to install the Oracle Client.

The Oracle 11.2.0.1 Client is required regardless of the version of the database server.

### **Sun Java Development Kit Version 6.0 Update 18 64-bit**

This software is only required for WebLogic installations.

Solaris Java packages used in the test cycle were downloaded from:

<http://java.sun.com/products/archive/index.html>

The Web server requires the 64-bit Java platform in order to function. Ensure that you install the 64-bit JDK. For Sun this involves installing the 32-bit java and then installing the 64-bit java patch.

Ensure that the environment variable JAVA\_HOME is set, and that "java" can be found in cissys user PATH variable.

### **Hibernate 3.3.2**

Hibernate must be installed prior to the installation of Oracle Utilities Meter Data Management.

Please download the file hibernate-3.3.2.ga.zip from the following link:

<http://prdownloads.sourceforge.net/hibernate/>

or from the following link:

[http://sourceforge.net/project/showfiles.php?group\\_id=40712&package\\_id=127784](http://sourceforge.net/project/showfiles.php?group_id=40712&package_id=127784)

It is very important that you download the exact version, as the product has only been certified with this exact release.

You will need to create a permanent directory to place one of the files from hibernate-3.3.2.ga.zip. (e.g. \opt\hibernate3.3.2).

Extract the file hibernate3.jar from hibernate-3.3.2.ga.zip.

### **Oracle WebLogic 11gR1 (10.3.3) 64-bit**

Oracle WebLogic software can be downloaded from the Oracle web site. This application server will run as a 64-bit application. This application server will run as a 64-bit application.

- Download and install 64-bit Java (as documented above) before installing WebLogic.
- Download and install WebLogic Server 11gR1 (10.3.3).

## Windows 2008 Application Server

This section describes the software requirements for operating the application using the Windows application server.

### Supported Application Servers

Operating System	Chipsets	Application Server
		<b>Oracle WebLogic 11gR1 (10.3.3)</b>
Windows 2008 Server SP2 (64-bit)	x86_64	64-bit version

### Web/Application Server Tier

#### Oracle 11.2.0.1 Client

The Java JDBC drivers must be installed as part of the client install.

Ensure that the userid cissys has been setup to be able to communicate with the Oracle database.

Use the command:

```
tnsping $ORACLE_SID
```

Use the cissys account to install the Oracle Client.

The Oracle 11.2.0.1 Client is required regardless of the version of the database server.

#### Sun Java Development Kit version 6.0 Update 18 64-bit

At time of release, Solaris Java packages could be obtained from:

<http://java.sun.com/products/archive/index.html>

The Web server requires the 64-bit Java platform. The main prerequisite for the Web server is the version of java mentioned above.

For the userid cissys, ensure that the environment variable JAVA\_HOME is setup, and that "java" can be found in cissys' PATH variable.

<http://www.oracle.com/technology/software/products/jdev/index.html>

#### Hibernate 3.3.2

Hibernate must be installed prior to the installation of Oracle Utilities Meter Data Management.

Please download the file hibernate-3.3.2.ga.zip from the following link:

<http://prdownloads.sourceforge.net/hibernate/>

or from the following link:

[http://sourceforge.net/project/showfiles.php?group\\_id=40712&package\\_id=127784](http://sourceforge.net/project/showfiles.php?group_id=40712&package_id=127784)

It is very important that you download the exact version, as the product has only been certified with this exact release.

You will need to create a permanent directory to place one of the files from hibernate-3.3.2.ga.zip. (e.g. \opt\hibernate3.3.2).

Extract the file hibernate3.jar from hibernate-3.3.2.ga.zip.

**Oracle WebLogic 11gR1 (10.3.3) 64-bit**

Oracle WebLogic software can be downloaded from the Oracle web site. This application server will run as a 64-bit application. This application server will run as a 64-bit application.

- Download and install 64-bit Java (as documented above) before installing WebLogic.
- Download and install WebLogic Server 11gR1 (10.3.3).



# Chapter 7

---

## Installing the Application Server Component of Oracle Utilities Application Framework

Installing the Oracle Utilities Application Framework is the prerequisite and foundation for installing a framework-based application such as Oracle Utilities Meter Data Management. This section describes the process for installing the Oracle Utilities Application Framework, including:

- **Installation Overview**
- **Preinstallation Tasks**
- **Installing Oracle Utilities Application Framework**

## Installation Overview

This process replaces any previously delivered and installed version of the Oracle Utilities Application Framework Server. Before you proceed:

1. Make sure that you have installed all the required third-party software as described in **Chapter 6: Installing Application Server Prerequisite Software**.
2. Complete the database installation (refer to the Oracle Utilities Meter Data Management *Database Administrator's Guide*).

The application server installation process of any framework-based application consists of the following:

1. Oracle Utilities Application Framework installation
2. Oracle Utilities Meter Data Framework application installation
3. Oracle Utilities Meter Data Management application installation

As a first step of the application server installation, the framework application server installation package must be downloaded and installed. The application server environment is created and configured by the framework installation process.

Once the Oracle Utilities Application Framework installation is successfully completed and the framework application environment is created, the Oracle Utilities Meter Data Framework can be installed on top of the framework environment.

You can download the installation packages from the Oracle E-Delivery site.

This section describes how to install a working Oracle Utilities Application Framework Server, which can then be further configured manually to allow for production performance levels.

Application server installation packages delivered for this version are multi-platform and are ready to install on any supported platform (as described in the section **Supported Platforms** on page 3-5). You must complete the database installation before installing the application server.

# Preinstallation Tasks

## Hardware and Software Version Prerequisites

The section **Supported Platforms** on page 3-5 contains all of the available platforms that are required with this release of the product.

## Database Installation

Verify that the database has been installed and is operational. See Oracle Utilities Meter Data Management *Database Administrator's Guide* for more information.

## Installation Prerequisites

**Chapter 6: Installing Application Server Prerequisite Software** describes all preparations that need to be done on the server prior to installing the application server. Please read carefully the server setup requirements and make sure that all prerequisite software is installed and that all required environment variables are set. Correct server setup and proper environment variable settings are an essential prerequisite for successful environment installation.

## System Architecture Overview

Oracle Utilities Application Framework V4.0.2 is a decoupled system architecture involving a Business Service Application tier and a Web Application tier. Typically both will run on the same server, but the design does allow each tier to be installed on separate servers.

The design implements a stateless session bean (EJB technology, under Java EE 5), to provide remote access to service invocations. The root Web app and XAI Web apps can be configured to access service processing locally (as in previous versions), or to make a remote EJB call to perform the service request. In the latter case, the served containers, effectively, run as very thin servlet wrappers around the remote call.

For all supported application servers except for WebLogic expanded configuration (SDK environment), the deployment is in the form of two Enterprise Archive (ear) Files: SPLService.ear and SPLWeb.ear. Web Archive (war) files are created during the installation process but are not deployed.

## Copying and Decompressing Install Media

The Oracle Utilities Application Framework installation file is delivered in jar format for both UNIX and Windows platforms.

If you are planning to install multiple Oracle Utilities Framework environments operated by different Oracle Utilities Administrator user ids, you must complete each of the following installation steps for each Administrator userid.

1. Log in to the application server host as the Oracle Utilities Framework administrator user ID (default ceases).
2. Create a temporary directory such as c:\ouaf\temp or /ouaf/temp. (Referred to below as <TEMPDIR>.)

This directory must be located outside any current or other working Oracle Utilities application environment. All files that are placed in this directory as a part of the installation can be deleted after completing a successful installation.

3. Copy the file FW-V4.0.2-MultiPlatform.jar from the delivered package to the <TEMPDIR>. If you are using FTP to transfer this file, remember to use the BINARY option for the FTP transfer.

4. Decompress the file:

```
cd <TEMPDIR>  
  
jar -xvf FW-V4.0.2-MultiPlatform.jar
```

Note: You will need to have Java JDK installed on the machine used to (un)jar the application server installation package. Please install the JDK that is supported for the install on your platform to be able to use the jar command. This is the location of Java packages: <http://java.sun.com/products/archive/index.html>

A sub-directory named “FW.V4.0.2” is created. It contains the installation software for the Oracle Utilities framework application server.

## Set Permissions for the cistab File in UNIX

Every Oracle Utilities Application Framework environment installed on a server must be registered in the /etc/cistab file located on that server. On UNIX servers, generally only the root user ID has write permissions to the /etc directory. Since the installation process is run by the Oracle administrator user ID (cissys), this user ID may not be able to write to /etc/cistab table.

The install utility checks permissions and if it identifies a lack of the necessary permissions, it generates a script in the <TEMPDIR>/FW.V4.0.2 directory named cistab\_<SPLENVIRON>.sh. Run the generated script using the root account before continuing with the installation process. The script initializes the cistab file in /etc directory (if it is the first Oracle Utilities Framework application environment on the server) and registers a new environment.

The generated script also changes the owner of /etc/cistab file to the Oracle Utilities Framework administrator user ID, so that the next time a new environment is created by the same Oracle Utilities Framework administrator user ID, you do not need to run the generated script with the root user ID. Instead the install utility itself proceeds with the registration.

If you are reinstalling an existing environment, only the validation of /etc/cistab entry is done by the install utility, no new registration occurs. The install utility interactively instructs you about every step that needs to occur in each specific case.

If you are planning to upgrade an existing environment it is your responsibility to take a backup prior to the installation process. The installation utility does not create a backup of existing environment.

# Installing Oracle Utilities Application Framework

This section outlines the steps for installing the Application Framework.

## Brief Description of the Installation Process

1. Log on as the Oracle Utilities Framework administrator (the default is cissys on UNIX) or as a user with Administrator privileges (on Windows).
2. Configure your application server and any third-party software required for your platform, as outlined in **Chapter 6: Installing Application Server Prerequisite Software**.

For example, create all environment variables such as HIBERNATE\_JAR\_DIR, JAVA\_HOME, etc.

3. Change directory to the <TEMPDIR>/FW.V4.0.2 directory.
4. Start the application installation utility by executing the appropriate script:

Note: Ensure that Perl 5.10 is in the PATH environment variable before executing the script.

**UNIX:** ksh ./install.sh

**Windows:** install.cmd

5. Follow the messages and instructions that are produced by the application installation utility. Use the completed worksheets in the section **Application Framework Installation and Configuration Worksheets** on page 4-5 to assist you.
6. Installation of Oracle Utilities Framework Application Server is complete if no errors occurred during installation.

## Detailed Description of the Installation Process

1. Log on to the host server as Oracle Utilities Application Framework administrator.  
Logon as cissys (on UNIX) or as a user with Administrator privileges (on Windows)
2. Configure application server and third-party software.  
Complete all steps outlined in **Chapter 6: Installing Application Server Prerequisite Software** such as setting the required environment variables (such as HIBERNATE\_JAR and JAVA\_HOME). You will need to obtain specific information for the install.
3. Change directory to the <TEMPDIR>/FW.V4.0.2 directory and start the application installation utility by executing the appropriate script:

**UNIX:** ksh ./install.sh

**Windows:** install.cmd

4. On the Environment Installation Options menu, select item 1: Third Party Software Configuration.  
Use the completed Third Party Software Configuration worksheet to complete this step. See **Application Framework Installation and Configuration Worksheets** on page 4-5.
5. Select menu item 50: Environment Installation Options.  
Use the completed Environment Installation Options Worksheet to complete this step. See **Application Framework Installation and Configuration Worksheets** on page 4-5.

Note: You must create the directory for output (the Log Mount Point). The installation process fails if this directory does not exist.

- Specify the environment name and the environment directory names for a new installation on a menu screen.
  - Specify the type of the database your environment will be connected to (the default will be Oracle).
  - Specify the Web Application Server your environment will run with (the default will be WebLogic).
  - Specify if this environment will be used for the Oracle Utilities Customer Care and Billing or Oracle Enterprise Taxation Management product. Enter **N** if this environment will be used for Oracle Utilities Business Intelligence, Oracle Utilities Mobile Workforce Management, or Oracle Utilities Meter Data Management.
  - Enter **P** to accept the selected options.
  - During this step, the specification of a new environment is checked for validity against /etc/cistab and the permissions on mount points and directories.
6. The application installation utility copies the installation media to a new environment.
- The installation utility copies the new version software from the temporary installation media directory to the new environment.
  - If any manual or electronic interruption occurs during this step, you can rerun the install utility from the beginning and follow the interactive instructions. The application installation utility is able to recover from such a failure.
7. Configure environment parameters.
- During this step you will configure environment parameters such as Web server hosts and ports, database name, and userid.
  - The application installation utility shows default values for some configuration options.
  - Use the completed Environment Configuration Worksheet to assist you.
- Note: Every option requires a value for a successful install. It is important to provide all values.
- When you are done with the parameters setup, proceed with the option **P. Write Configuration File**
  - You will be warned if you did not edit a section. You may proceed if you want to keep the default settings.
  - On completion of this step, \$SPLEBASE/etc/ENVIRON.INI file is created. This file contains the specific environment profile parameters and their values.
8. Set up environment variables.

Once the ENVIRON.INI file is created and contains the correct environment parameters, the application installation utility starts a sub shell to the current process by executing the splenviron.sh (on UNIX) or splenviron.cmd (on Windows) script, located in \$SPLEBASE/bin (or %SPLEBASE%\etc for Windows) directory. This script sets up all the necessary environment variables and shell settings for the application server to function correctly.

From this point, a number of environment variables have been set up. Some key ones are:

- \$PATH - an adjustment to \$PATH is made so that all of the environment scripts and objects will be in the path.
- \$SPLEBASE (%SPLEBASE%) - stands for <SPLEDIR>/<SPLENVIRON> directory
- \$SPLEOUTPUT (%SPLEOUTPUT%) - stands for <SPLEDIROUT>/<SPLENVIRON> directory

Note: Make sure that this directory exists. Otherwise the installation script will fail.

- `$SPLENVIRON (%SPLENVIRON%)` - environment name

For future operations or any post installation steps, you need to first execute the following command to connect your session to the new environment:

**UNIX:** `$SPLEBASE/bin/splenvron.sh -e $SPLENVIRON`

**Windows:** `%SPLEBASE%\bin\splenvron.cmd -e %SPLENVIRON%`

You need to execute this script each time you want to be connected to the specific environment before performing manual operations such as shutdown, startup or performing an additional application product installation.

When you have finished the install process, your current online session will be connected to the new environment.

9. Generate environment configuration parameters:

The application installation utility executes the script `initialSetup.sh` (on UNIX) or `initialSetup.cmd` (on Windows), located in `$SPLEBASE/bin` (`%SPLEBASE%\bin` on Windows) directory. This script populates different application configuration files with the new environment variables values and completes the rest of the installation steps.

Note: The `initialSetup` script encrypts the user ID and password values in the configuration files that it creates.

See the section **Chapter 4: Planning the Installation** for settings and configuration.



# Chapter 8

---

## Installing the Application Server Component of Oracle Utilities Meter Data Framework

Installing the Oracle Utilities Meter Data Framework is a prerequisite for installing Oracle Utilities Meter Data Management. This section describes the process for installing the Oracle Utilities Meter Data Framework on top of the previously created Oracle Utilities Application Framework environment. This section includes:

- **Preinstallation Tasks**
- **Installing Oracle Utilities Meter Data Framework**

To proceed with the Oracle Utilities Meter Data Framework installation you need to be connected to the target framework application environment. See the detailed installation instructions in the following section.

You must initialize the Framework environment along with the required set of patches prior to proceeding with the Oracle Utilities Meter Data Framework application installation. For detailed instructions see **Preparing for the Installation** on page 8-4.

## Preinstallation Tasks

This section describes the steps that should be taken before installing the Oracle Utilities Meter Data Framework.

### Installing Prerequisite Patches

The following Oracle Utilities Application Framework patches must be installed prior to installing Oracle Utilities Meter Data Framework 2.0.0:

9822242  
9616703  
9661228  
9684590  
9689949  
9737372  
9767325  
9775120  
9801416  
9811585  
9826081  
9828777  
9829641  
9829895  
9835285  
9838405  
9847638  
9849771  
9657424  
9686955  
9793243  
9703273  
9832763  
9838096  
9577485  
9838068  
9841089  
9845537  
9846267  
9855596  
9862979  
9389603  
9853242  
9446572  
9797052  
9791887  
9493372  
9718849  
9835477  
9841515  
9849466  
9857116  
9846319  
9784805  
9864001  
9866988  
9885429  
9626855  
9657459  
9825724  
9837273  
9837552

---

9862636  
9870968  
9884859  
9900362  
9436021  
9456718  
9593928  
9793666  
9900913  
9901017  
9910358  
9889194  
9929460  
9814068  
9911983

These patches are available as a convenience rollup along with this Media Pack. Please refer to the instructions contained inside the rollup directory for steps to install the patches in a single group. These patches are also available for download separately from My Oracle Support.

## Copying and Decompressing Install Media

The installation file is delivered in jar format for both UNIX and Windows platforms.

Oracle Utilities Meter Data Framework is delivered as a separate installation package. Please refer to **Supported Platforms** on page 3-5 for installation details regarding the database and operating system versions supported for the Meter Data Framework. Also see **Chapter 6: Installing Application Server Prerequisite Software** for prerequisite third-party software installation instructions.

Download the installation package and proceed as follows:

1. Log in to the host server as the Oracle Utilities Application Framework administrator user ID (default `cissys`). This is the same user ID that was used to install the Oracle Utilities Application Framework.
2. Create a `<TEMPDIR>` directory on the host server, which is independent of any current or other working Oracle Utilities Meter Data Framework application environment. This can be the same `<TEMPDIR>` used during the installation of the Oracle Utilities Application Framework.
3. Copy the file `MDF-V2.0.0-MultiPlatform.jar` in the delivered package to a `<TEMPDIR>` on your host server. If you are using FTP to transfer this file, remember to use the `BINARY` option for the FTP transfer.
4. Decompress the file:

```
cd <TEMPDIR>
jar -xvf MDF-V2.0.0-MultiPlatform.jar
```

For Windows installations, include the location of the JDK in your path before you execute the `jar` command.

For both Unix and Windows platforms, a sub-directory named `MDF.V2.0.0` is created. The contents of the installation directory are identical for both platforms. The directory contains the install software for the application.

# Installing Oracle Utilities Meter Data Framework

This section outlines the steps for installing the Meter Data Framework.

## Preparing for the Installation

1. Log on as Oracle Utilities Meter Data Framework Administrator (default cissys).
2. Initialize the Framework environment that you want to install the product into.

**UNIX:**

```
$SPLEBASE/bin/splenvirom.sh -e $SPLENVIRON
```

**Windows:**

```
%SPLEBASE%\bin\splenvirom.cmd -e %SPLENVIRON%
```

3. Stop the environment if running.

**UNIX:**

```
$SPLEBASE/bin/spl.sh stop
```

**Windows:**

```
%SPLEBASE%\bin\spl.cmd stop
```

## Installing the Application

1. Change to the <TEMPDIR>/MDEV2.0.0 Directory.
2. Execute the script:

**UNIX:**

```
ksh ./install.sh
```

**Windows:**

```
install.cmd
```

**Note:** On UNIX, ensure that you have the proper execute permission on install.sh

3. Choose option P to proceed with the installation: Write Configure file.

# Chapter 9

---

## Installing the Application Server Component of Oracle Utilities Meter Data Management

This section describes the procedure for installing Oracle Utilities Meter Data Management on top of the previously installed Oracle Utilities Meter Data Framework environment. This section includes:

- **Preinstallation Tasks**
- **Installing the Application**
- **Installing User Documentation**
- **Operating the Application**

To proceed with the Oracle Utilities Meter Data Management installation you need to be connected to the target Oracle Utilities Meter Data Framework application environment. See the detailed installation instructions in the following section.

You *must* initialize the Meter Data Framework environment. For detailed instructions see **Preparing for the Installation** on page 9-2.

## Preinstallation Tasks

This section describes the steps that should be taken before installing Oracle Utilities Meter Data Management.

### Installation Prerequisite

The Oracle Utilities Meter Data Framework 2.0.0 application must be installed prior to installing Oracle Utilities Meter Data Management 2.0.0:

### Copying and Decompressing Install Media

The installation file is delivered in jar format for both UNIX and Windows platforms.

Oracle Utilities Meter Data Management is delivered as a separate installation package. Please refer to the **Supported Platforms** on page 3-5 for versions and installation details regarding the database and operating system. Also see **Chapter 6: Installing Application Server Prerequisite Software** for prerequisite third-party software installation instructions.

Download the installation package and proceed as follows:

1. Log in to the host server as the Oracle Utilities Meter Data Framework administrator user ID (default `ciissys`). This is the same user ID that was used to install the Oracle Utilities Meter Data Framework.
2. Create a `<TEMPDIR>` directory on the host server, which is independent of any current or other working Oracle Utilities Meter Data Management application environment. This can be the same `<TEMPDIR>` used during the installation of the Oracle Utilities Meter Data Framework.
3. Copy the file `MDM-V2.0.0-MultiPlatform.jar` in the delivered package to a `<TEMPDIR>` on your host server. If you are using FTP to transfer this file, remember to use the `BINARY` option for the FTP transfer.

4. Decompress the file:

```
cd <TEMPDIR>

jar -xvf MDM-V2.0.0-MultiPlatform.jar
```

For Windows installations, include the location of the JDK in your path before you execute the jar command.

For both Unix and Windows platforms, a sub-directory named `MDM.V2.0.0` is created. The contents of the installation directory are identical for both platforms. The directory contains the install software for the application product.

### Preparing for the Installation

1. Log on as Oracle Utilities Meter Data Management Administrator (default `ciissys`).
2. Initialize the Framework environment that you want to install the product into.

#### UNIX:

```
$$PLEBASE/bin/splenvron.sh -e $$PLENVIRON
```

#### Windows:

```
%$PLEBASE%\bin\splenvron.cmd -e %$PLENVIRON%
```

3. Stop the environment if running.

**UNIX:**

```
$SPLEBASE/bin/spl.sh stop
```

**Windows:**

```
%SPLEBASE%\bin\spl.cmd stop
```

## Installing the Application

1. Change to the <TEMPDIR>/MDM.V2.0.0 directory.
2. Execute the install script:

**UNIX:**

```
ksh ./install.sh
```

**Windows:**

```
install.cmd
```

Note: On UNIX, ensure that you have the proper execute permission on install.sh.

3. Choose option P to proceed with the installation.
4. Once the install has finished successfully, you will need to execute Post Installation steps:

### Post Installation steps:

1. Run the configureEnv script to change the configuration.

**UNIX:**

```
$ cd $SPLEBASE  
$ ksh ./configureEnv.sh
```

**Windows:**

```
C:\> cd %SPLEBASE%  
C:\> configureEnv.cmd
```

2. Choose option P to write the configuration.
3. Run the initialSetup script.

**UNIX:**

```
$ cd $SPLEBASE  
$ ksh ./initialSetup.sh
```

**Windows:**

```
C:\> cd %SPLEBASE%  
C:\> initialSetup.cmd
```

**Note:** The above steps are mandatory for the initial installation of Oracle Utilities Meter Data Management

4. Start up the environment. Run the following command:

**UNIX:** spl.sh start

**Windows:** spl.cmd start

Follow the messages on the screen along with the logs in \$SPLSYSTEMLOGS directory to ensure that the environment was started successfully.

If the startup failed, identify the problem by reviewing the logs. Resolve any issues before attempting to restart the environment.

You should postpone the startup process until you are done with post installation steps.

(See the note below:)

Use the following utility to stop the environment:

**UNIX:** spl.sh stop

**Windows:** spl.cmd stop

**Note:** The first time you start Oracle Utilities Meter Data Management, you need to log in to the WebLogic console and give system access to cisusers role. The WebLogic console application can be accessed through the following URL:

`http://<hostname>:<portname>/console`

## Installing User Documentation

This section provides instructions for installing the Oracle Utilities Meter Data Management user documentation that is supplied with the system. The Oracle Utilities Meter Data Management user documentation is provided in PDF format for printing.

The documentation is also provided in HTML format located inside the Oracle Utilities Meter Data Management application server installation package. It is automatically installed and can be launched from the user interface. The files are under the applications directory packaged in the file named help.war. User documentation is provided in English (ENG). The documentation material is divided into the following subdirectories underneath the language directory:

- D1: Oracle Utilities Meter Data Framework User Guide
- D2: Oracle Utilities Meter Data Management User Guide
- F1: Oracle Utilities Application Framework Administration and Business Process Guides

## Installing Stand-Alone Online Help

You can also use the Oracle Utilities Meter Data Management online help in stand-alone mode (that is, you do not have to launch it from the Oracle Utilities Meter Data Management application or access it on the application server).

To install the Oracle Utilities Meter Data Management help for stand-alone operation, copy the help.war from the Oracle Utilities Meter Data Management server (environment) or from the Oracle Utilities Meter Data Management installation package to the server or machine on which you want to access the help. If you want to copy the file from any installed Oracle Utilities Meter Data Management environment, you can locate the file in the \$SPLBASE/splapp/applications directory on the server.

Unzip the help.war file to any directory on your machine. To launch the Oracle Utilities Meter Data Management help in stand-alone mode, open the SPLHelp.html file (located inside the language directory that you wish to use).

Note. Do not change the subdirectory names. The documents use relative path names to link to other documents. Changing the subdirectory names will result in broken links.

## Customizing Help for Stand-Alone Operation

You can customize the SPLHelp.html file to open to the file and topic that you most frequently use. To do so, edit the SPLHelp.html file and change the DEFAULT\_BOOKMARK to the desired location. The default DEFAULT\_BOOKMARK is 'helpHome.html'.

## Installing Stand-Alone Help Under Web Server

You can also install Oracle Utilities Meter Data Management online help as a stand-alone web application. You can use any Web Application server like WebLogic. Configure the configuration file for your web application server to use web application help.

For example,

- For WebLogic, configure config.xml file for deployed application Name="help" with URI="help.war" and set WebServer DefaultWebApp="help"
- For WebSphere, configure application.xml with module id="WebModule\_help" and <web-uri>help.war</web-uri>
- For Tomcat, configure server.xml with Context path="/help" and docBase= full path of help.war file

Access the documentation from the browser by the following URL:

http://<host name>:<port name>/<WebContext>/<Lang>/SPLHelp.html, where <hostname>:<portname> is the URL of the web server, <Web Context> is the root web context name specified during Web application server configuration, <Lang> is the name of the language directory, for example, ENG.

Note: Stand-alone online help files are not automatically updated when changes are made to the help files on the application server. You will have to re-install the stand-alone online help files.

## Operating the Application

At this point your installation and custom integration process is complete.

Be sure to read the *Oracle Utilities Meter Data Management Server Administration Guide* for more information on further configuring and operating the Oracle Utilities Meter Data Management system.



# Chapter 10

---

## Additional Tasks

This section describes tasks that should be completed after installing Oracle Utilities Meter Data Management, including:

- **Customizing Configuration Files**
- **Generating the Application Viewer**
- **Building Javadocs Indexes**
- **Configuring the Environment for Batch Processing**
- **Customizing the Logo**

## Customizing Configuration Files

You may wish to make customer modifications to various configuration files. To do so, you should locate the configuration file you want to customize and edit it manually.

Configuration files are generated from delivered templates in the Oracle Utilities installation and are populated by values entered by the installation utility during the configuration process. In future upgrades of Oracle Utilities application software versions, some templates may be changed to reflect new software version requirements. In this case, the upgrade process will back up your customized configuration file and will regenerate a configuration file based on a new template. You will need to review the new configuration file and apply your customized changes back if still applicable for the new version.

For configuration files that are located in a Web application (for example, web.xml, hibernate.properties), of the Web application during installation process, you will not be able to edit the configuration files directly.

You will need to follow the procedure:

- Locate the configuration file you want to customize in the directory \$SPLEBASE/etc/conf.
- Apply your changes.

## Generating the Application Viewer

You may extend Application Viewer capabilities within an environment by generating additional items. The additional items that can be generated include algorithm type and related algorithm information, maintenance object information and data dictionary information.

This section details the steps necessary to generate the additional items.

1. Shut down the environment.
2. Initialize a command shell:

The scripts that are provided with the system need to be run from a shell prompt on the machine that you installed the application on. Before such scripts can be run the shell must be “initialized” by running the splenviron script provided with the system.

### For Windows:

The command window should be opened on the Windows server that you installed the application on.

In the below example you should replace the variables:

%SPLEBASE% with the Full directory name that you installed the application into  
and

%SPLENVIRON% with the name you gave to the environment at installation time.

To initialize the environment type the following in your command prompt:

```
%SPLEBASE%\bin\splenviron.cmd -e %SPLENVIRON%
```

For example:

```
D:\ouaf\TEST_ENVIRON1\bin\splenviron.cmd -e TEST_ENVIRON1
```

### For Unix:

You will need to logon to your UNIX box as the Oracle Utilities Administrator (default cissys) and open a shell prompt.

In the below example you should replace the variables

\$\$SPLEBASE with the Full directory name that you installed the application into  
and

\$\$SPLENVIRON with the name you gave to the environment at installation time.

To initialize the environment type:

```
$$SPLEBASE/bin/splenviron.sh -e $$SPLENVIRON
```

For example:

```
/ouaf/TEST_ENVIRON1/bin/splenviron.sh -e TEST_ENVIRON1
```

3. Execute the script to generate all information

Execute the following command for your operating system

### UNIX:

```
ksh $$SPLEBASE/bin/genappvieweritems.sh
```

### Windows:

```
%SPLEBASE%\bin\genappvieweritems.cmd
```

4. Restart your application

## Building Javadocs Indexes

The following script allows rebuilding the Javadocs indexes in the appViewer java module. This is necessary after Customer Modifications have been applied to an environment. (This needs to be run only if the Customer Modification includes Java Code.)

**Windows:**

```
%SPLEBASE%\bin\buildJavadocsIndex.cmd
```

**UNIX:**

```
ksh $SPLEBASE/bin/buildJavadocsIndex.sh
```

## Configuring the Environment for Batch Processing

See the *Batch Server Administration Guide* for information on configuring the environment for batch processing.

## Customizing the Logo

The customer may want to replace the Oracle Utilities logo image on the Main menu with another logo image. To do this, put the logo <customer\_logo\_file>.gif file into the directory \$SPLEBASE/etc/conf/root/cm and create a new “External” Navigation Key called CM\_logoImage. To do that, run the Oracle Utilities application from the browser with the parameters: http://<hostname>:<port>/cis.jsp?utilities=true&tools=true. From the Admin menu, select Navigation Key. Add the above Navigation Key with its corresponding URL Override path. The syntax for the URL path is:

**For Windows:** http://<host name>:<port>/<Web Context>/cm/<customer\_logo\_file>.gif

**For UNIX:** http://<host name>:<port>/<Web Context>/cm/<customer\_logo\_file>.gif.

The root directory may be deployed in war file format for runtime environment (SPLApp.war). Use provided utilities to incorporate your cm directory into SPLApp.war file.

# Appendix A

---

## License and Copyright Notices

License and Copyright notices for associated products:

### Third Party Products

#### Notice concerning usage of ANTLR

Oracle Corporation has used ANTLR in developing this software.

#### Notice concerning usage of Apache Software

The following are covered under the Apache 2.0 license.

- Apache Axis
- Cgilib
- Commons-BeanUtils
- Commons-Codec
- Commons-Collections
- Commons-HttpClient
- Commons-lang
- Commons-logging
- Commons-Fileupload
- Commons-IO
- Log4j
- Maven
- Qdox
- Tomcat
- Velocity
- Woodstox XML processor
- StAX

/\*

\* Copyright 1999-2004 The Apache Software Foundation.

\*

---

```
* Licensed under the Apache License, Version 2.0 (the "License");
* you may not use this file except in compliance with the License.
* You may obtain a copy of the License at
*
*   http://www.apache.org/licenses/LICENSE-2.0
*
* Unless required by applicable law or agreed to in writing, software
* distributed under the License is distributed on an "AS IS" BASIS,
* WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or
implied.
* See the License for the specific language governing permissions and
* limitations under the License.
*/
```

## Apache License

Version 2.0, January 2004

<http://www.apache.org/licenses/>

### TERMS AND CONDITIONS FOR USE, REPRODUCTION, AND DISTRIBUTION

#### 1. Definitions.

"License" shall mean the terms and conditions for use, reproduction, and distribution as defined by Sections 1 through 9 of this document.

"Licensor" shall mean the copyright owner or entity authorized by the copyright owner that is granting the License.

"Legal Entity" shall mean the union of the acting entity and all other entities that control, are controlled by, or are under common control with that entity. For the purposes of this definition, "control" means (i) the power, direct or indirect, to cause the direction or management of such entity, whether by contract or otherwise, or (ii) ownership of fifty percent (50%) or more of the outstanding shares, or (iii) beneficial ownership of such entity.

"You" (or "Your") shall mean an individual or Legal Entity exercising permissions granted by this License.

"Source" form shall mean the preferred form for making modifications, including but not limited to software source code, documentation source, and configuration files.

"Object" form shall mean any form resulting from mechanical transformation or translation of a Source form, including but not limited to compiled object code, generated documentation, and conversions to other media types.

"Work" shall mean the work of authorship, whether in Source or Object form, made available under the License, as indicated by a copyright notice that is included in or attached to the work (an example is provided in the Appendix below).

"Derivative Works" shall mean any work, whether in Source or Object form, that is based on (or derived from) the Work and for which the editorial revisions, annotations, elaborations, or other modifications represent, as a whole, an original work of authorship. For the purposes of this License, Derivative Works shall not include works that remain separable from, or merely link (or bind by name) to the interfaces of, the Work and Derivative Works thereof.

"Contribution" shall mean any work of authorship, including the original version of the Work and any modifications or additions to that Work or Derivative Works thereof, that is intentionally submitted to Licensor for inclusion in the Work by the copyright owner or by an individual or Legal Entity authorized to submit on behalf of the copyright owner. For the purposes of this definition, "submitted" means any form of electronic, verbal, or written communication sent to the Licensor or its representatives, including but not limited to communication on electronic mailing lists, source code control systems, and issue tracking systems that are managed by, or on

---

behalf of, the Licensor for the purpose of discussing and improving the Work, but excluding communication that is conspicuously marked or otherwise designated in writing by the copyright owner as "Not a Contribution."

"Contributor" shall mean Licensor and any individual or Legal Entity on behalf of whom a Contribution has been received by Licensor and subsequently incorporated within the Work.

2. Grant of Copyright License. Subject to the terms and conditions of this License, each Contributor hereby grants to You a perpetual, worldwide, non-exclusive, no-charge, royalty-free, irrevocable copyright license to reproduce, prepare Derivative Works of, publicly display, publicly perform, sublicense, and distribute the Work and such Derivative Works in Source or Object form.

3. Grant of Patent License. Subject to the terms and conditions of this License, each Contributor hereby grants to You a perpetual, worldwide, non-exclusive, no-charge, royalty-free, irrevocable (except as stated in this section) patent license to make, have made, use, offer to sell, sell, import, and otherwise transfer the Work, where such license applies only to those patent claims licensable by such Contributor that are necessarily infringed by their Contribution(s) alone or by combination of their Contribution(s) with the Work to which such Contribution(s) was submitted. If You institute patent litigation against any entity (including a cross-claim or counterclaim in a lawsuit) alleging that the Work or a Contribution incorporated within the Work constitutes direct or contributory patent infringement, then any patent licenses granted to You under this License for that Work shall terminate as of the date such litigation is filed.

4. Redistribution. You may reproduce and distribute copies of the Work or Derivative Works thereof in any medium, with or without modifications, and in Source or Object form, provided that You meet the following conditions:

You must give any other recipients of the Work or Derivative Works a copy of this License; and  
You must cause any modified files to carry prominent notices stating that You changed the files; and

You must retain, in the Source form of any Derivative Works that You distribute, all copyright, patent, trademark, and attribution notices from the Source form of the Work, excluding those notices that do not pertain to any part of the Derivative Works; and

If the Work includes a "NOTICE" text file as part of its distribution, then any Derivative Works that You distribute must include a readable copy of the attribution notices contained within such NOTICE file, excluding those notices that do not pertain to any part of the Derivative Works, in at least one of the following places: within a NOTICE text file distributed as part of the Derivative Works; within the Source form or documentation, if provided along with the Derivative Works; or, within a display generated by the Derivative Works, if and wherever such third-party notices normally appear. The contents of the NOTICE file are for informational purposes only and do not modify the License. You may add Your own attribution notices within Derivative Works that You distribute, alongside or as an addendum to the NOTICE text from the Work, provided that such additional attribution notices cannot be construed as modifying the License.

You may add Your own copyright statement to Your modifications and may provide additional or different license terms and conditions for use, reproduction, or distribution of Your modifications, or for any such Derivative Works as a whole, provided Your use, reproduction, and distribution of the Work otherwise complies with the conditions stated in this License.

5. Submission of Contributions. Unless You explicitly state otherwise, any Contribution intentionally submitted for inclusion in the Work by You to the Licensor shall be under the terms and conditions of this License, without any additional terms or conditions. Notwithstanding the above, nothing herein shall supersede or modify the terms of any separate license agreement you may have executed with Licensor regarding such Contributions.

6. Trademarks. This License does not grant permission to use the trade names, trademarks, service marks, or product names of the Licensor, except as required for reasonable and customary use in describing the origin of the Work and reproducing the content of the NOTICE file.

---

7. Disclaimer of Warranty. Unless required by applicable law or agreed to in writing, Licensor provides the Work (and each Contributor provides its Contributions) on an "AS IS" BASIS, WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied, including, without limitation, any warranties or conditions of TITLE, NON-INFRINGEMENT, MERCHANTABILITY, or FITNESS FOR A PARTICULAR PURPOSE. You are solely responsible for determining the appropriateness of using or redistributing the Work and assume any risks associated with Your exercise of permissions under this License.

8. Limitation of Liability. In no event and under no legal theory, whether in tort (including negligence), contract, or otherwise, unless required by applicable law (such as deliberate and grossly negligent acts) or agreed to in writing, shall any Contributor be liable to You for damages, including any direct, indirect, special, incidental, or consequential damages of any character arising as a result of this License or out of the use or inability to use the Work (including but not limited to damages for loss of goodwill, work stoppage, computer failure or malfunction, or any and all other commercial damages or losses), even if such Contributor has been advised of the possibility of such damages.

9. Accepting Warranty or Additional Liability. While redistributing the Work or Derivative Works thereof, You may choose to offer, and charge a fee for, acceptance of support, warranty, indemnity, or other liability obligations and/or rights consistent with this License. However, in accepting such obligations, You may act only on Your own behalf and on Your sole responsibility, not on behalf of any other Contributor, and only if You agree to indemnify, defend, and hold each Contributor harmless for any liability incurred by, or claims asserted against, such Contributor by reason of your accepting any such warranty or additional liability.

END OF TERMS AND CONDITIONS

## Notice concerning usage of ASM

Copyright (c) 2000-2005 INRIA, France Telecom

All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
3. Neither the name of the copyright holders nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

---

## Notice concerning usage of CruiseControl

CruiseControl, a Continuous Integration Toolkit

Copyright (c) 2001, ThoughtWorks, Inc.

651 W Washington Ave. Suite 600

Chicago, IL 60661 USA

All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.

Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

Neither the name of ThoughtWorks, Inc., CruiseControl, nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE REGENTS OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

## Notice concerning usage of dom4j

BSD style license

Redistribution and use of this software and associated documentation ("Software"), with or without modification, are permitted provided that the following conditions are met:

1. Redistributions of source code must retain copyright statements and notices. Redistributions must also contain a copy of this document.
2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
3. The name "DOM4J" must not be used to endorse or promote products derived from this Software without prior written permission of MetaStuff, Ltd. For written permission, please contact [dom4j-info@metastuff.com](mailto:dom4j-info@metastuff.com).
4. Products derived from this Software may not be called "DOM4J" nor may "DOM4J" appear in their names without prior written permission of MetaStuff, Ltd. DOM4J is a registered trademark of MetaStuff, Ltd.
5. Due credit should be given to the DOM4J Project - <http://www.dom4j.org>

---

THIS SOFTWARE IS PROVIDED BY METASTUFF, LTD. AND CONTRIBUTORS ``AS IS" AND ANY EXPRESSED OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL METASTUFF, LTD. OR ITS CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

Copyright 2001-2005 (C) MetaStuff, Ltd. All Rights Reserved.

## Notice concerning usage of Ehcache

The Apache Software License, Version 1.1

Copyright (c) 2000 The Apache Software Foundation. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
3. The end-user documentation included with the redistribution, if any, must include the following acknowledgment:

"This product includes software developed by the Apache Software Foundation (<http://www.apache.org/>)."

Alternately, this acknowledgment may appear in the software itself, if and wherever such third-party acknowledgments normally appear.

4. The names "Apache" and "Apache Software Foundation" must not be used to endorse or promote products derived from this software without prior written permission. For written permission, please contact [apache@apache.org](mailto:apache@apache.org).
5. Products derived from this software may not be called "Apache", nor may "Apache" appear in their name, without prior written permission of the Apache Software Foundation.

THIS SOFTWARE IS PROVIDED ``AS IS" AND ANY EXPRESSED OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE APACHE SOFTWARE FOUNDATION OR ITS CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

=====  
=====

---

This software consists of voluntary contributions made by many individuals on behalf of the Apache Software Foundation. For more information on the Apache Software Foundation, please see <<http://www.apache.org/>>.

Portions of this software are based upon public domain software originally written at the National Center for Supercomputing Applications, University of Illinois, Urbana-Champaign.

## Notices concerning usage of Hibernate and c3p0

GNU LESSER GENERAL PUBLIC LICENSE

Version 2.1, February 1999

Copyright (C) 1991, 1999 Free Software Foundation, Inc.

51 Franklin St, Fifth Floor, Boston, MA 02110-1301 USA

Everyone is permitted to copy and distribute verbatim copies of this license document, but changing it is not allowed.

[This is the first released version of the Lesser GPL. It also counts as the successor of the GNU Library Public License, version 2, hence the version number 2.1.]

Preamble

The licenses for most software are designed to take away your freedom to share and change it. By contrast, the GNU General Public Licenses are intended to guarantee your freedom to share and change free software--to make sure the software is free for all its users.

This license, the Lesser General Public License, applies to some specially designated software packages--typically libraries--of the Free Software Foundation and other authors who decide to use it. You can use it too, but we suggest you first think carefully about whether this license or the ordinary General Public License is the better strategy to use in any particular case, based on the explanations below.

When we speak of free software, we are referring to freedom of use, not price. Our General Public Licenses are designed to make sure that you have the freedom to distribute copies of free software (and charge for this service if you wish); that you receive source code or can get it if you want it; that you can change the software and use pieces of it in new free programs; and that you are informed that you can do these things.

To protect your rights, we need to make restrictions that forbid distributors to deny you these rights or to ask you to surrender these rights. These restrictions translate to certain responsibilities for you if you distribute copies of the library or if you modify it.

For example, if you distribute copies of the library, whether gratis or for a fee, you must give the recipients all the rights that we gave you. You must make sure that they, too, receive or can get the source code. If you link other code with the library, you must provide complete object files to the recipients, so that they can relink them with the library after making changes to the library and recompiling it. And you must show them these terms so they know their rights.

We protect your rights with a two-step method: (1) we copyright the library, and (2) we offer you this license, which gives you legal permission to copy, distribute and/or modify the library.

To protect each distributor, we want to make it very clear that there is no warranty for the free library. Also, if the library is modified by someone else and passed on, the recipients should know that what they have is not the original version, so that the original author's reputation will not be affected by problems that might be introduced by others.

Finally, software patents pose a constant threat to the existence of any free program. We wish to make sure that a company cannot effectively restrict the users of a free program by obtaining a restrictive license from a patent holder. Therefore, we insist that any patent license obtained for a version of the library must be consistent with the full freedom of use specified in this license.

---

Most GNU software, including some libraries, is covered by the ordinary GNU General Public License. This license, the GNU Lesser General Public License, applies to certain designated libraries, and is quite different from the ordinary General Public License. We use this license for certain libraries in order to permit linking those libraries into non-free programs.

When a program is linked with a library, whether statically or using a shared library, the combination of the two is legally speaking a combined work, a derivative of the original library. The ordinary General Public License therefore permits such linking only if the entire combination fits its criteria of freedom. The Lesser General Public License permits more lax criteria for linking other code with the library.

We call this license the "Lesser" General Public License because it does Less to protect the user's freedom than the ordinary General Public License. It also provides other free software developers Less of an advantage over competing non-free programs. These disadvantages are the reason we use the ordinary General Public License for many libraries. However, the Lesser license provides advantages in certain special circumstances.

For example, on rare occasions, there may be a special need to encourage the widest possible use of a certain library, so that it becomes a de-facto standard. To achieve this, non-free programs must be allowed to use the library. A more frequent case is that a free library does the same job as widely used non-free libraries. In this case, there is little to gain by limiting the free library to free software only, so we use the Lesser General Public License.

In other cases, permission to use a particular library in non-free programs enables a greater number of people to use a large body of free software. For example, permission to use the GNU C Library in non-free programs enables many more people to use the whole GNU operating system, as well as its variant, the GNU/Linux operating system.

Although the Lesser General Public License is Less protective of the users' freedom, it does ensure that the user of a program that is linked with the Library has the freedom and the wherewithal to run that program using a modified version of the Library.

The precise terms and conditions for copying, distribution and modification follow. Pay close attention to the difference between a "work based on the library" and a "work that uses the library". The former contains code derived from the library, whereas the latter must be combined with the library in order to run.

#### TERMS AND CONDITIONS FOR COPYING, DISTRIBUTION AND MODIFICATION

0. This License Agreement applies to any software library or other program which contains a notice placed by the copyright holder or other authorized party saying it may be distributed under the terms of this Lesser General Public License (also called "this License"). Each licensee is addressed as "you".

A "library" means a collection of software functions and/or data prepared so as to be conveniently linked with application programs (which use some of those functions and data) to form executables.

The "Library", below, refers to any such software library or work which has been distributed under these terms. A "work based on the Library" means either the Library or any derivative work under copyright law: that is to say, a work containing the Library or a portion of it, either verbatim or with modifications and/or translated straightforwardly into another language. (Hereinafter, translation is included without limitation in the term "modification".)

"Source code" for a work means the preferred form of the work for making modifications to it. For a library, complete source code means all the source code for all modules it contains, plus any associated interface definition files, plus the scripts used to control compilation and installation of the library.

Activities other than copying, distribution and modification are not covered by this License; they are outside its scope. The act of running a program using the Library is not restricted, and output from such a program is covered only if its contents constitute a work based on the Library

---

(independent of the use of the Library in a tool for writing it). Whether that is true depends on what the Library does and what the program that uses the Library does.

1. You may copy and distribute verbatim copies of the Library's complete source code as you receive it, in any medium, provided that you conspicuously and appropriately publish on each copy an appropriate copyright notice and disclaimer of warranty; keep intact all the notices that refer to this License and to the absence of any warranty; and distribute a copy of this License along with the Library.

You may charge a fee for the physical act of transferring a copy, and you may at your option offer warranty protection in exchange for a fee.

2. You may modify your copy or copies of the Library or any portion of it, thus forming a work based on the Library, and copy and distribute such modifications or work under the terms of Section 1 above, provided that you also meet all of these conditions:

a) The modified work must itself be a software library.

b) You must cause the files modified to carry prominent notices stating that you changed the files and the date of any change.

c) You must cause the whole of the work to be licensed at no charge to all third parties under the terms of this License.

d) If a facility in the modified Library refers to a function or a table of data to be supplied by an application program that uses the facility, other than as an argument passed when the facility is invoked, then you must make a good faith effort to ensure that, in the event an application does not supply such function or table, the facility still operates, and performs whatever part of its purpose remains meaningful.

(For example, a function in a library to compute square roots has a purpose that is entirely well-defined independent of the application. Therefore, Subsection 2d requires that any application-supplied function or table used by this function must be optional: if the application does not supply it, the square root function must still compute square roots.)

These requirements apply to the modified work as a whole. If identifiable sections of that work are not derived from the Library, and can be reasonably considered independent and separate works in themselves, then this License, and its terms, do not apply to those sections when you distribute them as separate works. But when you distribute the same sections as part of a whole which is a work based on the Library, the distribution of the whole must be on the terms of this License, whose permissions for other licensees extend to the entire whole, and thus to each and every part regardless of who wrote it.

Thus, it is not the intent of this section to claim rights or contest your rights to work written entirely by you; rather, the intent is to exercise the right to control the distribution of derivative or collective works based on the Library.

In addition, mere aggregation of another work not based on the Library with the Library (or with a work based on the Library) on a volume of a storage or distribution medium does not bring the other work under the scope of this License.

3. You may opt to apply the terms of the ordinary GNU General Public License instead of this License to a given copy of the Library. To do this, you must alter all the notices that refer to this License, so that they refer to the ordinary GNU General Public License, version 2, instead of to this License. (If a newer version than version 2 of the ordinary GNU General Public License has appeared, then you can specify that version instead if you wish.) Do not make any other change in these notices.

Once this change is made in a given copy, it is irreversible for that copy, so the ordinary GNU General Public License applies to all subsequent copies and derivative works made from that copy.

This option is useful when you wish to copy part of the code of the Library into a program that is not a library.

---

4. You may copy and distribute the Library (or a portion or derivative of it, under Section 2) in object code or executable form under the terms of Sections 1 and 2 above provided that you accompany it with the complete corresponding machine-readable source code, which must be distributed under the terms of Sections 1 and 2 above on a medium customarily used for software interchange.

If distribution of object code is made by offering access to copy from a designated place, then offering equivalent access to copy the source code from the same place satisfies the requirement to distribute the source code, even though third parties are not compelled to copy the source along with the object code.

5. A program that contains no derivative of any portion of the Library, but is designed to work with the Library by being compiled or linked with it, is called a "work that uses the Library". Such a work, in isolation, is not a derivative work of the Library, and therefore falls outside the scope of this License.

However, linking a "work that uses the Library" with the Library creates an executable that is a derivative of the Library (because it contains portions of the Library), rather than a "work that uses the library". The executable is therefore covered by this License. Section 6 states terms for distribution of such executables.

When a "work that uses the Library" uses material from a header file that is part of the Library, the object code for the work may be a derivative work of the Library even though the source code is not. Whether this is true is especially significant if the work can be linked without the Library, or if the work is itself a library. The threshold for this to be true is not precisely defined by law.

If such an object file uses only numerical parameters, data structure layouts and accessors, and small macros and small inline functions (ten lines or less in length), then the use of the object file is unrestricted, regardless of whether it is legally a derivative work. (Executables containing this object code plus portions of the Library will still fall under Section 6.)

Otherwise, if the work is a derivative of the Library, you may distribute the object code for the work under the terms of Section 6. Any executables containing that work also fall under Section 6, whether or not they are linked directly with the Library itself.

6. As an exception to the Sections above, you may also combine or link a "work that uses the Library" with the Library to produce a work containing portions of the Library, and distribute that work under terms of your choice, provided that the terms permit modification of the work for the customer's own use and reverse engineering for debugging such modifications.

You must give prominent notice with each copy of the work that the Library is used in it and that the Library and its use are covered by this License. You must supply a copy of this License. If the work during execution displays copyright notices, you must include the copyright notice for the Library among them, as well as a reference directing the user to the copy of this License. Also, you must do one of these things:

a) Accompany the work with the complete corresponding machine-readable source code for the Library including whatever changes were used in the work (which must be distributed under Sections 1 and 2 above); and, if the work is an executable linked with the Library, with the complete machine-readable "work that uses the Library", as object code and/or source code, so that the user can modify the Library and then relink to produce a modified executable containing the modified Library. (It is understood that the user who changes the contents of definitions files in the Library will not necessarily be able to recompile the application to use the modified definitions.)

b) Use a suitable shared library mechanism for linking with the Library. A suitable mechanism is one that (1) uses at run time a copy of the library already present on the user's computer system, rather than copying library functions into the executable, and (2) will operate properly with a modified version of the library, if the user installs one, as long as the modified version is interface-compatible with the version that the work was made with.

---

c) Accompany the work with a written offer, valid for at least three years, to give the same user the materials specified in Subsection 6a, above, for a charge no more than the cost of performing this distribution.

d) If distribution of the work is made by offering access to copy from a designated place, offer equivalent access to copy the above specified materials from the same place.

e) Verify that the user has already received a copy of these materials or that you have already sent this user a copy.

For an executable, the required form of the "work that uses the Library" must include any data and utility programs needed for reproducing the executable from it. However, as a special exception, the materials to be distributed need not include anything that is normally distributed (in either source or binary form) with the major components (compiler, kernel, and so on) of the operating system on which the executable runs, unless that component itself accompanies the executable.

It may happen that this requirement contradicts the license restrictions of other proprietary libraries that do not normally accompany the operating system. Such a contradiction means you cannot use both them and the Library together in an executable that you distribute.

7. You may place library facilities that are a work based on the Library side-by-side in a single library together with other library facilities not covered by this License, and distribute such a combined library, provided that the separate distribution of the work based on the Library and of the other library facilities is otherwise permitted, and provided that you do these two things:

a) Accompany the combined library with a copy of the same work based on the Library, uncombined with any other library facilities. This must be distributed under the terms of the Sections above.

b) Give prominent notice with the combined library of the fact that part of it is a work based on the Library, and explaining where to find the accompanying uncombined form of the same work.

8. You may not copy, modify, sublicense, link with, or distribute the Library except as expressly provided under this License. Any attempt otherwise to copy, modify, sublicense, link with, or distribute the Library is void, and will automatically terminate your rights under this License. However, parties who have received copies, or rights, from you under this License will not have their licenses terminated so long as such parties remain in full compliance.

9. You are not required to accept this License, since you have not signed it. However, nothing else grants you permission to modify or distribute the Library or its derivative works. These actions are prohibited by law if you do not accept this License. Therefore, by modifying or distributing the Library (or any work based on the Library), you indicate your acceptance of this License to do so, and all its terms and conditions for copying, distributing or modifying the Library or works based on it.

10. Each time you redistribute the Library (or any work based on the Library), the recipient automatically receives a license from the original licensor to copy, distribute, link with or modify the Library subject to these terms and conditions. You may not impose any further restrictions on the recipients' exercise of the rights granted herein. You are not responsible for enforcing compliance by third parties with this License.

11. If, as a consequence of a court judgment or allegation of patent infringement or for any other reason (not limited to patent issues), conditions are imposed on you (whether by court order, agreement or otherwise) that contradict the conditions of this License, they do not excuse you from the conditions of this License. If you cannot distribute so as to satisfy simultaneously your obligations under this License and any other pertinent obligations, then as a consequence you may not distribute the Library at all. For example, if a patent license would not permit royalty-free redistribution of the Library by all those who receive copies directly or indirectly through you, then the only way you could satisfy both it and this License would be to refrain entirely from distribution of the Library.

---

If any portion of this section is held invalid or unenforceable under any particular circumstance, the balance of the section is intended to apply, and the section as a whole is intended to apply in other circumstances.

It is not the purpose of this section to induce you to infringe any patents or other property right claims or to contest validity of any such claims; this section has the sole purpose of protecting the integrity of the free software distribution system which is implemented by public license practices. Many people have made generous contributions to the wide range of software distributed through that system in reliance on consistent application of that system; it is up to the author/donor to decide if he or she is willing to distribute software through any other system and a licensee cannot impose that choice.

This section is intended to make thoroughly clear what is believed to be a consequence of the rest of this License.

12. If the distribution and/or use of the Library is restricted in certain countries either by patents or by copyrighted interfaces, the original copyright holder who places the Library under this License may add an explicit geographical distribution limitation excluding those countries, so that distribution is permitted only in or among countries not thus excluded. In such case, this License incorporates the limitation as if written in the body of this License.

13. The Free Software Foundation may publish revised and/or new versions of the Lesser General Public License from time to time. Such new versions will be similar in spirit to the present version, but may differ in detail to address new problems or concerns.

Each version is given a distinguishing version number. If the Library specifies a version number of this License which applies to it and "any later version", you have the option of following the terms and conditions either of that version or of any later version published by the Free Software Foundation. If the Library does not specify a license version number, you may choose any version ever published by the Free Software Foundation.

14. If you wish to incorporate parts of the Library into other free programs whose distribution conditions are incompatible with these, write to the author to ask for permission. For software which is copyrighted by the Free Software Foundation, write to the Free Software Foundation; we sometimes make exceptions for this. Our decision will be guided by the two goals of preserving the free status of all derivatives of our free software and of promoting the sharing and reuse of software generally.

#### NO WARRANTY

15. BECAUSE THE LIBRARY IS LICENSED FREE OF CHARGE, THERE IS NO WARRANTY FOR THE LIBRARY, TO THE EXTENT PERMITTED BY APPLICABLE LAW. EXCEPT WHEN OTHERWISE STATED IN WRITING THE COPYRIGHT HOLDERS AND/OR OTHER PARTIES PROVIDE THE LIBRARY "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE. THE ENTIRE RISK AS TO THE QUALITY AND PERFORMANCE OF THE LIBRARY IS WITH YOU. SHOULD THE LIBRARY PROVE DEFECTIVE, YOU ASSUME THE COST OF ALL NECESSARY SERVICING, REPAIR OR CORRECTION.

16. IN NO EVENT UNLESS REQUIRED BY APPLICABLE LAW OR AGREED TO IN WRITING WILL ANY COPYRIGHT HOLDER, OR ANY OTHER PARTY WHO MAY MODIFY AND/OR REDISTRIBUTE THE LIBRARY AS PERMITTED ABOVE, BE LIABLE TO YOU FOR DAMAGES, INCLUDING ANY GENERAL, SPECIAL, INCIDENTAL OR CONSEQUENTIAL DAMAGES ARISING OUT OF THE USE OR INABILITY TO USE THE LIBRARY (INCLUDING BUT NOT LIMITED TO LOSS OF DATA OR DATA BEING RENDERED INACCURATE OR LOSSES SUSTAINED BY YOU OR THIRD PARTIES OR A FAILURE OF THE LIBRARY TO OPERATE WITH ANY OTHER SOFTWARE), EVEN IF SUCH HOLDER OR OTHER PARTY HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

## Notice concerning usage of International Components for Unicode (ICU4J)

ICU License - ICU 1.8.1 and later

COPYRIGHT AND PERMISSION NOTICE Copyright (c) 1995-2003 International Business Machines Corporation and others All rights reserved. Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, provided that the above copyright notice(s) and this permission notice appear in all copies of the Software and that both the above copyright notice(s) and this permission notice appear in supporting documentation.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT OF THIRD PARTY RIGHTS. IN NO EVENT SHALL THE COPYRIGHT HOLDER OR HOLDERS INCLUDED IN THIS NOTICE BE LIABLE FOR ANY CLAIM, OR ANY SPECIAL INDIRECT OR CONSEQUENTIAL DAMAGES, OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE. Except as contained in this notice, the name of a copyright holder shall not be used in advertising or otherwise to promote the sale, use or other dealings in this Software without prior written authorization of the copyright holder.

-----  
All trademarks and registered trademarks mentioned herein are the property of their respective owners.

## Notice concerning usage of fcrypt

/ crypto/des/fcrypt.c /

/ Copyright (C) 1996 Eric Young (eay@mincom.oz.au)

All rights reserved.

This package is an SSL implementation written by Eric Young (eay@mincom.oz.au).

The implementation was written so as to conform with Netscapes SSL.

This library is free for commercial and non-commercial use as long as the following conditions are adhered to. The following conditions apply to all code found in this distribution, be it the RC4, RSA, lhash, DES, etc., code; not just the SSL code. The SSL documentation included with this distribution is covered by the same copyright terms except that the holder is Tim Hudson (tjh@mincom.oz.au).

Copyright remains Eric Young's, and as such any Copyright notices in the code are not to be removed. If this package is used in a product, Eric Young should be given attribution as the author of the parts of the library used.

This can be in the form of a textual message at program startup or in documentation (online or textual) provided with the package.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

1. Redistributions of source code must retain the copyright notice, this list of conditions and the following disclaimer.

---

2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

3. All advertising materials mentioning features or use of this software must display the following acknowledgement: "This product includes cryptographic software written by Eric Young (eay@mincom.oz.au)"

The word 'cryptographic' can be left out if the routines from the library being used are not cryptographic related.

4. If you include any Windows specific code (or a derivative thereof) from the apps directory (application code) you must include an acknowledgement: "This product includes software written by Tim Hudson (tjh@mincom.oz.au)"

THIS SOFTWARE IS PROVIDED BY ERIC YOUNG ``AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED.

IN NO EVENT SHALL THE AUTHOR OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

The licence and distribution terms for any publically available version or derivative of this code cannot be changed. i.e. this code cannot simply be copied and put under another distribution licence [including the GNU Public Licence.]

## Notice concerning usage of Jaxen

Copyright 2003 (C) The Werken Company. All Rights Reserved.

Redistribution and use of this software and associated documentation ("Software"), with or without modification, are permitted provided that the following conditions are met:

1. Redistributions of source code must retain copyright statements and notices. Redistributions must also contain a copy of this document.
2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
3. The name "jaxen" must not be used to endorse or promote products derived from this Software without prior written permission of The Werken Company. For written permission, please contact bob@werken.com.
4. Products derived from this Software may not be called "jaxen" or may "jaxen" appear in their names without prior written permission of The Werken Company. "jaxen" is a registered trademark of The Werken Company.
5. Due credit should be given to The Werken Company. (<http://jaxen.werken.com/>).

THIS SOFTWARE IS PROVIDED BY THE WERKEN COMPANY AND CONTRIBUTORS ``AS IS" AND ANY EXPRESSED OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE WERKEN COMPANY OR ITS CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL,

---

EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

## Notice concerning usage of JOSSO

Copyright (c) 2004-2006, Novascope S.A. and the JOSSO team. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

\* Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.

\* Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

\* Neither the name of the JOSSO team nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

## Notice concerning usage of libjpeg

The authors make NO WARRANTY or representation, either express or implied, with respect to this software, its quality, accuracy, merchantability, or fitness for a particular purpose. This software is provided "AS IS", and you, its user, assume the entire risk as to its quality and accuracy.

This software is copyright (C) 1991-1998, Thomas G. Lane.

All Rights Reserved except as specified below.

Permission is hereby granted to use, copy, modify, and distribute this software (or portions thereof) for any purpose, without fee, subject to these

conditions:

(1) If any part of the source code for this software is distributed, then this README file must be included, with this copyright and no-warranty notice unaltered; and any additions, deletions, or changes to the original files must be clearly indicated in accompanying documentation.

---

(2) If only executable code is distributed, then the accompanying documentation must state that "this software is based in part on the work of the Independent JPEG Group".

(3) Permission for use of this software is granted only if the user accepts full responsibility for any undesirable consequences; the authors accept NO LIABILITY for damages of any kind.

These conditions apply to any software derived from or based on the IJG code, not just to the unmodified library. If you use our work, you ought to acknowledge us.

Permission is NOT granted for the use of any IJG author's name or company name in advertising or publicity relating to this software or products derived from it. This software may be referred to only as "the Independent JPEG Group's software".

We specifically permit and encourage the use of this software as the basis of commercial products, provided that all warranty or liability claims are assumed by the product vendor.

## Notice concerning usage of libproj4

Copyright (c) 2000, Frank Warmerdam

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies

or substantial portions of the Software. THE SOFTWARE IS PROVIDED "AS IS", WITHOUT

WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

## Notice concerning usage of libtiff

Copyright (c) 1988-1997 Sam Leffler

Copyright (c) 1991-1997 Silicon Graphics, Inc.

Permission to use, copy, modify, distribute, and sell this software and its documentation for any purpose is hereby granted without fee, provided that (i) the above copyright notices and this permission notice appear in all copies of the software and related documentation, and (ii) the names of Sam Leffler and Silicon Graphics may not be used in any advertising or publicity relating to the software without the specific, prior written permission of Sam Leffler and Silicon Graphics.

THE SOFTWARE IS PROVIDED "AS-IS" AND WITHOUT WARRANTY OF ANY KIND, EXPRESS, IMPLIED OR OTHERWISE, INCLUDING WITHOUT LIMITATION, ANY WARRANTY OF MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. IN NO EVENT SHALL SAM LEFFLER OR SILICON GRAPHICS BE LIABLE FOR ANY SPECIAL, INCIDENTAL, INDIRECT OR CONSEQUENTIAL DAMAGES OF ANY KIND, OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER OR NOT ADVISED OF THE POSSIBILITY OF DAMAGE,

---

AND ON ANY THEORY OF LIABILITY, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

## Notice concerning usage of MX4J

This product includes software developed by the MX4J project (<http://mx4j.sourceforge.net>).

The MX4J License, Version 1.0

Copyright (c) 2001-2004 by the MX4J contributors. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
3. The end-user documentation included with the redistribution, if any, must include the following acknowledgment:

"This product includes software developed by the MX4J project (<http://mx4j.sourceforge.net>)."

Alternately, this acknowledgment may appear in the software itself, if and wherever such third-party acknowledgments normally appear.

4. The name "MX4J" must not be used to endorse or promote products derived from this software without prior written permission. For written permission, please contact [biorn\\_steedom@users.sourceforge.net](mailto:biorn_steedom@users.sourceforge.net)
5. Products derived from this software may not be called "MX4J", nor may "MX4J" appear in their name, without prior written permission of Simone Bordet.

THIS SOFTWARE IS PROVIDED ``AS IS" AND ANY EXPRESSED OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE MX4J CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

## Notice concerning usage of PicoContainer

Copyright (c) 2003-2004, PicoContainer Organization

All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.

---

Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

Neither the name of the PicoContainer Organization nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

## Notice concerning usage of QDox

The license used for QDox is derived from the Apache Software License.

The IronSmith Software License, Version 1.1

(This license is derived and fully compatible with the Apache Software License - see <http://www.apache.org/LICENSE.txt>)

Copyright (c) 2002 The IronSmith Project. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
3. The end-user documentation included with the redistribution, if any, must include the following acknowledgment: "This product includes software developed by the IronSmith Project (<http://www.ironsmith.org/>).". Alternately, this acknowledgment may appear in the software itself, if and wherever such third-party acknowledgments normally appear.
4. The names "IronSmith" and "The IronSmith Project" must not be used to endorse or promote products derived from this software without prior written permission. For written permission, please contact [help@ironsmith.org](mailto:help@ironsmith.org).
5. Products derived from this software may not be called "IronSmith" or "QDox", nor may "IronSmith" or "QDox" appear in their name, without prior written permission of the IronSmith Project.

THIS SOFTWARE IS PROVIDED ``AS IS" AND ANY EXPRESSED OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE APACHE SOFTWARE FOUNDATION OR ITS CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF

---

USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

## Notice concerning usage of XStream

XStream is an open source software, made available under a BSD license.

Copyright (c) 2003-2005, Joe Walnes

All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

Neither the name of XStream nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

## Notice concerning usage of Perl

Perl Kit, Version 5

Copyright (C) 1993, 1994, 1995, 1996, 1997, 1998

1999, 2000, 2001, by Larry Wall and others

All rights reserved.

This program is free software; it is being redistributed under the terms of the "Artistic License".

### The Artistic License

Preamble

The intent of this document is to state the conditions under which a Package may be copied, such that the Copyright Holder maintains some semblance of artistic control over the development of the package, while giving the users of the package the right to use and distribute the Package in a more-or-less customary fashion, plus the right to make reasonable modifications.

Definitions:

"Package" refers to the collection of files distributed by the Copyright Holder, and derivatives of that collection of files created through textual modification.

---

"Standard Version" refers to such a Package if it has not been modified, or has been modified in accordance with the wishes of the Copyright Holder.

"Copyright Holder" is whoever is named in the copyright or copyrights for the package.

"You" is you, if you're thinking about copying or distributing this Package.

"Reasonable copying fee" is whatever you can justify on the basis of media cost, duplication charges, time of people involved, and so on. (You will not be required to justify it to the Copyright Holder, but only to the computing community at large as a market that must bear the fee.)

"Freely Available" means that no fee is charged for the item itself, though there may be fees involved in handling the item. It also means that recipients of the item may redistribute it under the same conditions they received it.

1. You may make and give away verbatim copies of the source form of the Standard Version of this Package without restriction, provided that you duplicate all of the original copyright notices and associated disclaimers.

2. You may apply bug fixes, portability fixes and other modifications derived from the Public Domain or from the Copyright Holder. A Package modified in such a way shall still be considered the Standard Version.

3. You may otherwise modify your copy of this Package in any way, provided that you insert a prominent notice in each changed file stating how and when you changed that file, and provided that you do at least ONE of the following:

1. place your modifications in the Public Domain or otherwise make them Freely Available, such as by posting said modifications to Usenet or an equivalent medium, or placing the modifications on a major archive site such as ftp.uu.net, or by allowing the Copyright Holder to include your modifications in the Standard Version of the Package.

2. use the modified Package only within your corporation or organization.

3. rename any non-standard executables so the names do not conflict with standard executables, which must also be provided, and provide a separate manual page for each non-standard executable that clearly documents how it differs from the Standard Version.

4. make other distribution arrangements with the Copyright Holder.

4. You may distribute the programs of this Package in object code or executable form, provided that you do at least ONE of the following:

a) distribute a Standard Version of the executables and library files, together with instructions (in the manual page or equivalent) on where to get the Standard Version.

b) accompany the distribution with the machine-readable source of the Package with your modifications.

c) accompany any non-standard executables with their corresponding Standard Version executables, giving the non-standard executables non-standard names, and clearly documenting the differences in manual pages (or equivalent), together with instructions on where to get the Standard Version.

d) make other distribution arrangements with the Copyright Holder.

5. You may charge a reasonable copying fee for any distribution of this Package. You may charge any fee you choose for support of this Package. You may not charge a fee for this Package itself. However, you may distribute this Package in aggregate with other (possibly commercial) programs as part of a larger (possibly commercial) software distribution provided that you do not advertise this Package as a product of your own.

6. The scripts and library files supplied as input to or produced as output from the programs of this Package do not automatically fall under the copyright of this Package, but belong to whomever generated them, and may be sold commercially, and may be aggregated with this Package.

---

7.C or perl subroutines supplied by you and linked into this Package shall not be considered part of this Package.

8.The name of the Copyright Holder may not be used to endorse or promote products derived from this software without specific prior written permission.

9.THIS PACKAGE IS PROVIDED "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, WITHOUT LIMITATION, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE.

The End

## Notice concerning usage of Mime-Base64 Perl Module

Copyright 1995-1999,2001-2004 Gisle Aas <gisle@ActiveState.com>

This library is free software; you can redistribute it and/or modify it under the same terms as Perl itself.

The standard version of the package that is used can be obtained from <http://www.cpan.org>. Specifically, the software can be obtained from the following link :

<http://search.cpan.org/search%3fmodule=MIME::Base64>

## Notice concerning usage of Mime-Lite Perl Module

This is MIME::Lite 3.01 Maintenance release

TERMS AND CONDITIONS

Copyright (c) 1997 by Eryq.

Copyright (c) 1998 by ZeeGee Software Inc.

Copyright (c) 2003 Yves Orton. demerphq (at) hotmail.com.

All rights reserved. This program is free software; you can redistribute it and/or modify it under the same terms as Perl itself.

This software comes with NO WARRANTY of any kind. See the COPYING file in the distribution for details.

The standard version of the package that is used can be obtained from <http://www.cpan.org>. Specifically, the software can be obtained from the following link :

<http://search.cpan.org/search%3fmodule=MIME::Lite>

## Notice concerning usage of DBD::DB2 Perl Module

License Agreement for DBD::DB2

---

PLEASE READ THIS AGREEMENT CAREFULLY BEFORE INSTALLING OR USING THIS PROGRAM. IF YOU INSTALL OR USE THIS PROGRAM, YOU AGREE TO THESE TERMS.

---

1. This DBD::DB2 code "Program" is owned by International Business Machines Corporation or its subsidiaries (IBM) or IBM's suppliers, and is copyrighted and licensed, not sold. IBM retains title to the Program, and grants the user of the Program "You" an:

irrevocable, worldwide, nonexclusive, perpetual, royalty-free and fully paid-up license

(i) to use, execute, display, perform, and reproduce the Program,

- 
- (ii) to prepare derivative works based on the Program,
    - (iii) to distribute copies of the Program and derivative works thereof, and
    - (iv) to authorize others to do all of the above.
  2. You must reproduce the copyright notice and any other legend of ownership on each copy or partial copy of the Program.
  3. IBM would appreciate receiving a copy of derivative works of the Program that You create. You may provide to IBM such derivative works pursuant to the terms of this Agreement and the directions in the README file contained within the Program directory. You represent and warrant to IBM that You are the sole author of, and/or have full exclusive right, title and interest to any and all derivative works You provide to IBM. You further represent that You are under no obligation to assign your rights in such derivative works to any third-party, including without limitation, any current or former employer.
  4. You agree that IBM may utilize all information, ideas, concepts, know-how or techniques furnished by You to IBM in connection with any derivative works You make or have made to the IBM Program, and that You provide to IBM and IBM may, but shall not be obligated to, include such derivative works in the IBM Program or in any IBM product without accounting to You.
  5. With respect to any derivative works of the Program You provide to IBM, You grant to IBM an:
    - irrevocable, worldwide, non-exclusive, perpetual, royalty--free and fully paid-up license
    - (i) to use, execute, display, perform, and reproduce your derivative works,
    - (ii) to prepare derivative works based upon your derivative works,
    - (iii) to distribute copies of your derivative works, and
    - (iv) to authorize others to do all of the above.
  6. YOU UNDERSTAND THAT THE PROGRAM IS BEING PROVIDED TO YOU "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO ANY IMPLIED WARRANTIES OF MERCHANTABILITY, QUALITY, PERFORMANCE, INTELLECTUAL PROPERTY INFRINGEMENT OR FITNESS FOR ANY PARTICULAR PURPOSE. IBM has no obligation to provide service, defect correction, or any maintenance for the Program. IBM has no obligation to supply any Program updates or enhancements to You even if such are or later become available.
  7. IBM accepts no liability for damages You may suffer as a result of your use of the Program. Under no circumstances is IBM liable for any of the following:
    1. third-party claims against You for losses or damages;
    2. loss of, or damage to, your records or data; or
    3. direct damages, lost profits, lost savings, incidental, special, or indirect damages or consequential damages, even if IBM or its authorized supplier, has been advised of the possibility of such damages.
  8. Some jurisdictions do not allow these limitations or exclusions, so they may not apply to You.
  9. You are responsible for the payment of any taxes resulting from this license.
  10. You agree not to bring a legal action more than two years after the cause of action arose.
  11. This license will be governed by and interpreted in accordance with the laws of the State of New York.
  12. This license is the only understanding and agreement IBM has for your use of the Program.

---

The standard version of the package that is used can be obtained from <http://www.cpan.org>. Specifically, the software can be obtained from the following link :

<http://search.cpan.org/search%3fmodule=DBD::DB2>

## Notice concerning usage of DBI Perl Module

DBI by Tim Bunce. This pod text by Tim Bunce, J. Douglas Dunlop, Jonathan Leffler and others. Perl by Larry Wall and the perl5-porters.

COPYRIGHT

The DBI module is Copyright (c) 1994-2004 Tim Bunce. Ireland.

All rights reserved.

This is distributed under the terms of the Artistic License.

The standard version of the package that is used can be obtained from <http://www.cpan.org>. Specifically, the software can be obtained from the following link :

<http://search.cpan.org/search%3fmodule=DBD::DB2>

## Notice concerning usage of JCIP Annotations

This software uses the JCIP Annotations library which is copyright (c) 2005 Brian Goetz and Tim Peierls and is released under the Creative Commons Attribution License (<http://creativecommons.org/licenses/by/2.5>). The official home for this software is <http://www.jcip.net>.

## Notice concerning usage of YUI Library

Software License Agreement (BSD License)

Copyright (c) 2009, Yahoo! Inc.

All rights reserved.

Redistribution and use of this software in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- Neither the name of Yahoo! Inc. nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission of Yahoo! Inc.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT

---

(INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.