

**Oracle Utilities Mobile Workforce
Management Business Intelligence**

Data Mapping Guide

Release 2.4.0

E26817-01

December 2011

Copyright © 2000, 2011, Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this software or related documentation is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, the following notice is applicable:

U.S. GOVERNMENT RIGHTS

Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, duplication, disclosure, modification, and adaptation shall be subject to the restrictions and license terms set forth in the applicable Government contract, and, to the extent applicable by the terms of the Government contract, the additional rights set forth in FAR 52.227-19, Commercial Computer Software License (December 2007). Oracle America, Inc., 500 Oracle Parkway, Redwood City, CA 94065.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications which may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

This software or hardware and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third party content, products and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third party content, products or services.

Contents

Contents

Preface	i-i
Audience	i-i
Related Documents	i-i
Typographical Conventions	i-ii
Chapter 1	
Overview	1-1
Terminologies	1-1
<Presentation Table Name>	1-1
Chapter 2	
Oracle Utilities Mobile Workforce Management Business Intelligence Data Maps	2-1
Dimension Extract Programs	2-2
Crew Time Usage Dimension	2-2
Shift Business Object Status Dimension	2-3
Task Business Object Status Dimension	2-5
Crew Shift Dimension	2-7
Crew Dimension	2-8
Task Type Dimension	2-10
Service Area Dimension	2-12
Appointment Time Dimension	2-14
Appointment Time of Day Dimension	2-15
Travel Duration Deviation Dimension	2-17
Late Logon Time Dimension	2-18
Early Logoff Time Dimension	2-20
Work Duration Deviation Dimension	2-22
Travel Distance Deviation Dimension	2-23
Response Time Deviation Dimension	2-25
Address Dimension	2-26
Fact Extract Programs	2-29
Crew Tasks Fact	2-29
Completed Shift Fact	2-32
Activity Fact	2-34
Dimension Table Schema	2-38
Crew Time Usage Dimension <CD_CREW_TM_USG>	2-38
Shift Business Object Status Dimension <CD_SHIFT_BO_STATUS>	2-39
Task Business Object Status Dimension <CD_TASK_BO_STATUS>	2-41
Crew Shift Dimension <CD_CREW_SHIFT>	2-43
Crew Dimension <CD_CREW>	2-44
Task Type Dimension <CD_TASK_TYPE>	2-46
Service Area Dimension <CD_SERVICE_AREA>	2-48
Appointment Time Dimension <CD_APPT_TM>	2-49

Appointment Time of Day Dimension <CD_APPT_TM_OF_DAY>	2-51
Travel Duration Deviation Dimension <CD_TRAVEL_DUR_DEV>	2-52
Late Logon Time Dimension <CD_LATE_LOGON_TM>	2-54
Early Logoff Time Dimension <CD_EARLY_LOGOFF_TM>	2-56
Work Duration Deviation Dimension <CD_WORK_DUR_DEV>	2-57
Travel Distance Deviation Dimension <CD_TRAVEL_DIST_DEV>	2-59
Response Time Deviation Dimension <CD_RESP_TM_DEV>	2-60
Address Dimension <CD_ADDR>	2-62
Fact Table Schema	2-65
Crew Tasks Fact <CF_CREW_TASK>.....	2-65
Completed Shift Fact <CF_CMP_SHIFT>	2-72
Field Activity Fact <CF_FLD_ACTIVITY>	2-77

Preface

This guide provides the data mapping information for Oracle Utilities Mobile Workforce Management Business Intelligence.

Audience

This guide is intended for all implementers of Oracle Utilities Mobile Workforce Management Business Intelligence.

Related Documents

For more information, see the following documents:

- *Oracle Utilities Advanced Spatial and Operational Analytics Installation Guide*
- *Oracle Utilities Advanced Spatial and Operational Analytics Quick Install Guide*
- *Oracle Utilities Advanced Spatial and Operational Analytics Release Notes*
- *Oracle Utilities Advanced Spatial and Operational Analytics User's Guide*
- *Oracle Utilities Advanced Spatial and Operational Analytics Administration Guide*

Oracle Utilities Business Intelligence Documentation Library:

- *Oracle Utilities Business Intelligence Quick Install Guide*
- *Oracle Utilities Business Intelligence Installation Guide*
- *Oracle Utilities Business Intelligence DBA Guide*
- *Oracle Utilities Business Intelligence User's Guide*

See Also:

- *Oracle Utilities Business Intelligence V2.4.0 Server Administration Guide*
- *Oracle Utilities Application Framework V4.1 Business Process Guide*
- *Oracle Utilities Application Framework V4.1 Administration Guide*

Typographical Conventions

The following text conventions are used in this document:

Convention	Meaning
boldface	Boldface type indicates graphical user interface elements associated with an action, or terms defined in text or the glossary.
<i>italic</i>	Italic type indicates book titles, emphasis, or placeholder variables for which you supply particular values.
monospace	Monospace type indicates commands within a paragraph, URLs, code in examples, text that appears on the screen, or text that you enter.

Chapter 1

Overview

This guide provides the data mapping for Oracle Utilities Mobile Workforce Management Business Intelligence.

This mapping document describes the data mapping between the source systems and the target, and the rules of data transformation for Oracle Utilities Mobile Workforce Analytics. The document captures business rules, data flow mapping, and data movement requirements.

Terminologies

The following terms are used for the data maps contained in this document.

<Presentation Table Name>

The Presentation Table Name lists the default name of the object in OBIEE when no customer modifications have been made to the name of the table. This is the default label seen in answers.

Properties

The Properties table lists properties of the table independent of each field. The following properties are listed in the table:

Property	Value
Load Table Name	Name of the data warehouse table that the extract file will be loaded into
Table Type	Fact or Dimension
Source System Driver Table	Name of the table in source database from which data is extracted
Source System Extract Program	Name of the program that will create the extract file
SCD Type	1 - Existing records are updated directly 2 - Existing records are marked inactive and new records are inserted from the staging file
Fact Type	Whether this is a snapshot or transactional fact table
Stage Table Name	Name of the table in the BI target database that can be used to query the data records from the staging file

Property	Value
Stage File name	Operating system file name that will contain the data records to be loaded into the table. The filename will end in '.DAT'
Control Table Name	Name of the table in the Oracle database that can be used to query the record from the control file
Control File Name	Name of the operating system file that is used as the control file in the extraction. The filename will end in '.CTL'. Control file stores the record count and batch control information. It is used in load validation.
Update Procedure Name	The name of an Oracle procedure that will be used run prior to loading records from the staging data file. Used by Type 2 dimensions to update the Effective End Date value for records that exist in the staging file.
OWB Map Name	Name of the mapping that loads records from the staging file into the database table
OWB Work Flow Name	Name of the process flow that will process the next available staging file and load the records in there into the database table
OWB Work Flow Package Name	Name of the process flow package that contains the process flow
Extract Procedure	Name of the extract program that will create the extract files

Fields

The Fields table lists the individual properties of each field in the Presentation Table or the Database Table. The following fields are listed in the tables:

Property	Value
Extract Field	Name of the field in the staging file that stores this data
Length	Length of the extract field in the staging file
Source	Field from source application or stage table or calculation is used to populate the extract field. If blank, then there is no default population of the field in the MWM extracts. If the field is from the source system driver table, then only the field name is mentioned. If the field is from the edge application, then it is prefixed by the edge application table name.

Property	Value
Column	Name of the column in the database table. If blank, then the field is not present in the database table, but is only available from OBIEE.
OBIEE Field	Name of the field in the OBIEE Presentation folder. If blank, then the field is not available by default in OBIEE.
Load	How the data is populated. If the Column field is entered, then this is how the data is loaded in OWB. If the column field is empty, then this contains the calculation in OBIEE that is used by the column.

Chapter 2

Oracle Utilities Mobile Workforce Management Business Intelligence Data Maps

This section contains data maps for the following Oracle Utilities Mobile Workforce Management data:

- **Dimension Extract Programs**
- **Fact Extract Programs**
- **Dimension Table Schema**
- **Fact Table Schema**

Note: The data source indicator needs to be configured on the source application as mentioned in the section “Note for Data Source Indicator” in Chapter 3, in *Oracle Utilities Advanced Spatial and Operational Analytics Administration Guide*.

Dimension Extract Programs

Crew Time Usage Dimension

This extract program retrieves values from the Extendable Lookup table in the Mobile Workforce Management source system to populate the Crew Time Usage dimension.

Properties

Property	Value
Load Table Name	CD_CREW_TM_USG
Table Type	Dimension
Source System Driver Table	F1_EXT_LOOKUP_VAL
Source System Extract Program - Initial Load	M1-CTUIL
Source System Extract Program - Extract	M1-CTUDX
Stage Table Name	STG_CREW_TM_USG_EXT
Stage File Name	D_CREW_TM_USAGE_EXT.DAT
Control Table Name	D_CREW_TM_USG_EXT.CTL
Control File name	D_CREW_TM_USAGE_EXT.CTL
Update Procedure Name	
OWB Map Name	SPLMAP_D_CREW_TM_USG
OWB Work Flow Name	SPLWF_D_CREW_TM_USG
OWB Work Flow Package Name	DIM_MWM

Fields (listed in the order they will appear in the flat file)

Extract Field	Length	Source
UPDATED_DTTM	20	Values: Initial Load: 1/1/2000, Incremental Load: Current Date
CHANGE_TYPE_CD	1	Values: I – Insert/Update, D – Deleted
CREW_TM_USG_CD	30	F1_EXT_LOOKUP_VALUE
CREW_TM_USG_DESCR	100	DESCR
PRODUCTIVITY_CD	4	FIELD_VALUE
PRODUCTIVITY_DESCR	100	DESCR
UDF1_CD	30	
UDF1_DESCR	60	
UDF2_CD	30	

Extract Field	Length	Source
UDF2_DESCR	60	
UDF3_CD	30	
UDF3_DESCR	60	
UDF4_CD	30	
UDF4_DESCR	60	
UDF5_CD	30	
UDF5_DESCR	60	
UDF6_CD	30	
UDF6_DESCR	60	
UDF7_CD	30	
UDF7_DESCR	60	
UDF8_CD	30	
UDF8_DESCR	60	
UDF9_CD	30	
UDF9_DESCR	60	
UDF10_CD	30	
UDF10_DESCR	60	
DATA_SOURCE_IND	6	Data Source Indicator value in MWM Feature Config

Shift Business Object Status Dimension

This extract program retrieves values from the Business Object Status table in the Mobile Workforce Management source system to populate the Shift Business Object Status dimension.

Properties

Property	Value
Load Table Name	CD_SHIFT_BO_STATUS
Table Type	Dimension
Source System Driver Table	F1_BUS_OBJ_STATUS
Source System Extract Program - Initial Load	M1-SBSIL
Source System Extract Program - Extract	M1-SBSDX
Stage Table Name	STG_SHIFT_BO_STATUS_EXT
Stage File Name	D_SHIFT_BO_STATUS_EXT.DAT

Property	Value
Control Table Name	STG_SHIFT_BO_STATUS_CTL_EXT
Control File name	D_SHIFT_BO_STATUS_EXT.CTL
Update Procedure Name	
OWB Map Name	SPLMAP_D_SHIFT_BO_STATUS
OWB Work Flow Name	SPLWF_D_SHIFT_BO_STATUS
OWB Work Flow Package Name	DIM_MWM

Fields (listed in the order they will appear in the flat file)

Extract Field	Length	Source
UPDATED_DTTM	20	Values: Initial Load: 1/1/2000, Incremental Load: Current Date
CHANGE_TYPE_CD	1	Values: I – Insert/Update, D – Deleted
BUS_OBJ_CD	30	BUS_OBJ_CD
BUS_OBJ_DESCR	100	DESCR
STATUS_CD	12	BO_STATUS_CD
STATUS_DESCR	100	DESCR
STATUS_COND_CD	4	BO_STATUS_COND_FLG
STATUS_COND_DESCR	100	DESCR
REASON_CD	30	BO_STATUS_REASON_CD
REASON_DESCR	100	DESCR
UDF1_CD	30	
UDF1_DESCR	60	
UDF2_CD	30	
UDF2_DESCR	60	
UDF3_CD	30	
UDF3_DESCR	60	
UDF4_CD	30	
UDF4_DESCR	60	
UDF5_CD	30	
UDF5_DESCR	60	
UDF6_CD	30	
UDF6_DESCR	60	
UDF7_CD	30	

Extract Field	Length	Source
UDF7_DESCR	60	
UDF8_CD	30	
UDF8_DESCR	60	
UDF9_CD	30	
UDF9_DESCR	60	
UDF10_CD	30	
UDF10_DESCR	60	
DATA_SOURCE_IND	6	Data Source Indicator value in MWM Feature Config

Task Business Object Status Dimension

This extract program retrieves values from the Business Object Status table in the Mobile Workforce Management source system to populate the Task BO Status dimension.

Properties

Property	Value
Load Table Name	CD_TASK_BO_STATUS
Table Type	Dimension
Source System Driver Table	F1_BUS_OBJ_STATUS
Source System Extract Program - Initial Load	M1-TBSIL
Source System Extract Program - Extract	M1-TBSDX
Stage Table Name	STG_TASK_BO_STATUS_EXT
Stage File Name	D_TASK_BO_STATUS_EXT.DAT
Control Table Name	STG_TASK_BO_STATUS_CTL_EXT
Control File name	D_TASK_BO_STATUS_EXT.CTL
Update Procedure Name	
OWB Map Name	OUBIMAP_D_TASK_BO_STATUS
OWB Work Flow Name	OUBIWF_D_TASK_BO_STATUS
OWB Work Flow Package Name	DIM_MWM

Fields (listed in the order they will appear in the flat file)

Extract Field	Length	Source
UPDATED_DTTM	20	Values: Initial Load: 1/1/2000, Incremental Load: Current Date
CHANGE_TYPE_CD	1	Values: I – Insert/Update, D – Deleted
BUS_OBJ_CD	30	BUS_OBJ_CD
BUS_OBJ_DESCR	100	DESCR
STATUS_CD	12	BO_STATUS_CD
STATUS_DESCR	100	DESCR
STATUS_COND_CD	4	BO_STATUS_COND_FLG
STATUS_COND_DESCR	100	DESCR
REASON_CD	30	BO_STATUS_REASON_CD
REASON_DESCR	100	DESCR
INCOMPLETE_IND	1	INCOMPLETE_IND
UDF1_CD	30	
UDF1_DESCR	60	
UDF2_CD	30	
UDF2_DESCR	60	
UDF3_CD	30	
UDF3_DESCR	60	
UDF4_CD	30	
UDF4_DESCR	60	
UDF5_CD	30	
UDF5_DESCR	60	
UDF6_CD	30	
UDF6_DESCR	60	
UDF7_CD	30	
UDF7_DESCR	60	
UDF8_CD	30	
UDF8_DESCR	60	
UDF9_CD	30	
UDF9_DESCR	60	
UDF10_CD	30	
UDF10_DESCR	60	

Extract Field	Length	Source
DATA_SOURCE_IND	6	Data Source Indicator value in MWM Feature Config

Crew Shift Dimension

This extract program retrieves values from the Crew Shift table in the Mobile Workforce Management source system to populate the Crew Shift dimension.

Properties

Property	Value
Load Table Name	CD_CREW_SHIFT
Table Type	Dimension
Source System Driver Table	M1_CREW_SHIFT
Source System Extract Program - Initial Load	M1-SFTIL
Source System Extract Program - Extract	M1-CRSDX
Stage Table Name	STG_CREW_SHIFT_EXT
Stage File Name	D_CREW_SHIFT_EXT.DAT
Control Table Name	STG_CREW_SHIFT_CTL_EXT
Control File name	D_CREW_SHIFT_EXT.CTL
Update Procedure Name	SPL_CREW_SHIFT_UPD_PRC
OWB Map Name	SPLMAP_D_CREW_SHIFT
OWB Work Flow Name	SPLWF_D_CREW_SHIFT
OWB Work Flow Package Name	DIM2

Fields (listed in the order they will appear in the flat file)

Extract Field	Length	Source
UPDATED_DTTM	20	Values: Initial Load: 1/1/2000, Incremental Load: Current Date
CHANGE_TYPE_CD	1	Values: I – Insert/Update, D – Deleted
SRC_CREW_SHIFT_ID	30	SHIFT_ID
CREW_SHIFT_INFO	254	CREW_SHIFT_INFO
CREW_SHIFT_TYPE_CD	30	CREW_SHIFT_TYPE_CD
CREW_SHIFT_TYPE_DESCR	100	DESCR

Extract Field	Length	Source
PRIMARY_FN_CD	30	SVC_CLS_CD
PRIMARY_FN_DESCR	100	DESCR
UDF1_CD	30	
UDF1_DESCR	60	
UDF2_CD	30	
UDF2_DESCR	60	
UDF3_CD	30	
UDF3_DESCR	60	
UDF4_CD	30	
UDF4_DESCR	60	
UDF5_CD	30	
UDF5_DESCR	60	
UDF6_CD	30	
UDF6_DESCR	60	
UDF7_CD	30	
UDF7_DESCR	60	
UDF8_CD	30	
UDF8_DESCR	60	
UDF9_CD	30	
UDF9_DESCR	60	
UDF10_CD	30	
UDF10_DESCR	60	
DATA_SOURCE_IND	6	Data Source Indicator value in MWM Feature Config

Crew Dimension

This extract program retrieves values from the Resource table in the Mobile Workforce Management source system to populate the Crew dimension.

Properties

Property	Value
Load Table Name	CD_CREW
Table Type	Dimension
Source System Driver Table	M1_RESRC

Property	Value
Source System Extract Program - Initial Load	M1-CREIL
Source System Extract Program - Extract	M1-CREDX
Stage Table Name	STG_CREW_EXT
Stage File Name	D_CREW_EXT.DAT
Control Table Name	STG_CREW_CTL_EXT
Control File name	D_CREW_EXT.CTL
Update Procedure Name	SPL_CREW_UPD_PRC
OWB Map Name	SPLMAP_D_CREW
OWB Work Flow Name	SPLWF_D_CREW
OWB Work Flow Package Name	DIM

Fields (listed in the order they will appear in the flat file)

Extract Field	Length	Source
UPDATED_DTTM	20	Values: Initial Load: 1/1/2000, Incremental Load: Current Date
CHANGE_TYPE_CD	1	Values: I – Insert/Update, D – Deleted
CREW_CD	30	RESRC_ID
CREW_DESCR	60	CREW_DESCR
SRC_CREW_ID	30	RESRC_ID
CREW_TYPE_CD	30	RESRC_TYPE_CD
CREW_TYPE_DESCR	100	DESCR
ORG_UNIT1_CD	4	F1_EXT_LOOKUP_VALUE
ORG_UNIT1_DESCR	100	DESCR
ORG_UNIT2_CD	4	F1_EXT_LOOKUP_VALUE
ORG_UNIT3_DESCR	100	DESCR
ORG_UNIT3_CD	4	F1_EXT_LOOKUP_VALUE
ORG_UNIT3_DESCR	100	DESCR
UDF1_CD	30	
UDF1_DESCR	60	
UDF2_CD	30	
UDF2_DESCR	60	
UDF3_CD	30	

Extract Field	Length	Source
UDF3_DESCR	60	
UDF4_CD	30	
UDF4_DESCR	60	
UDF5_CD	30	
UDF5_DESCR	60	
UDF6_CD	30	
UDF6_DESCR	60	
UDF7_CD	30	
UDF7_DESCR	60	
UDF8_CD	30	
UDF8_DESCR	60	
UDF9_CD	30	
UDF9_DESCR	60	
UDF10_CD	30	
UDF10_DESCR	60	
DATA_SOURCE_IND	6	Data Source Indicator value in MWM Feature Config

Task Type Dimension

This extract program retrieves values from the Task Type table in the Mobile Workforce Management source system to populate the Task Type dimension.

Properties

Property	Value
Load Table Name	CD_TASK_TYPE
Table Type	Dimension
Source System Driver Table	M1_TASK_TYPE
Source System Extract Program - Initial Load	M1-TKTIL
Source System Extract Program - Extract	M1-TKTDX
Stage Table Name	STG_TASK_TYPE_EXT
Stage File Name	D_TASK_TYPE_EXT.DAT
Control Table Name	STG_TASK_TYPE_CTL_EXT

Property	Value
Control File name	D_TASK_TYPE_EXT.CTL
Update Procedure Name	
OWB Map Name	SPLMAP_D_TASK_TYPE
OWB Work Flow Name	SPLWF_D_TASK_TYPE
OWB Work Flow Package Name	DIM_MWM

Fields (listed in the order they will appear in the flat file)

Extract Field	Length	Source
UPDATED_DTTM	20	Values: Initial Load: 1/1/2000, Incremental Load: Current Date
CHANGE_TYPE_CD	1	Values: I – Insert/Update, D – Deleted
TASK_TYPE_CD	30	TASK_TYPE_CD
TASK_TYPE_DESCR	100	DESCR
TASK_CLASS_CD	4	TASK_CLS_FLG
TASK_CLASS_DESCR	100	DESCR
PRIORITY_PROF_CD	30	PRI_PROF_CD
PRIORITY_PROF_DESCR	100	DESCR
SVC_CATEGORY_CD	30	SVC_CATEGORY_CD
SVC_CATEGORY_DESCR	100	DESCR
RESP_TM_SLA	15	RESP_TM_SLA
UDF1_CD	30	
UDF1_DESCR	60	
UDF2_CD	30	
UDF2_DESCR	60	
UDF3_CD	30	
UDF3_DESCR	60	
UDF4_CD	30	
UDF4_DESCR	60	
UDF5_CD	30	
UDF5_DESCR	60	
UDF6_CD	30	
UDF6_DESCR	60	

Extract Field	Length	Source
UDF7_CD	30	
UDF7_DESCR	60	
UDF8_CD	30	
UDF8_DESCR	60	
UDF9_CD	30	
UDF9_DESCR	60	
UDF10_CD	30	
UDF10_DESCR	60	
DATA_SOURCE_IND	6	Data Source Indicator value in MWM Feature Config

Service Area Dimension

This extract program retrieves values from the Service Area table in the Mobile Workforce Management source system to populate the Service Area dimension.

Properties

Property	Value
Load Table Name	CD_SERVICE_AREA
Table Type	Dimension
Source System Driver Table	M1_SVC_AREA
Source System Extract Program - Initial Load	M1-SERIL
Source System Extract Program - Extract	M1-SERDX
Stage Table Name	STG_SERVICE_AREA_EXT
Stage File Name	D_SERVICE_AREA_EXT.DAT
Control Table Name	STG_SERVICE_AREA_CTL_EXT
Control File name	D_SERVICE_AREA_EXT.CTL
Update Procedure Name	SPL_SERVICE_AREA_UPD_PRC
OWB Map Name	SPLMAP_D_ SERVICE_AREA
OWB Work Flow Name	SPLWF_D_ SERVICE_AREA
OWB Work Flow Package Name	DIM2

Fields (listed in the order they will appear in the flat file)

Extract Field	Length	Source
UPDATED_DTTM	20	Values: Initial Load: 1/1/2000, Incremental Load: Current Date
CHANGE_TYPE_CD	1	Values: I – Insert/Update, D – Deleted
SERVICE_AREA_CD	30	Service Area Code
SERVICE_AREA_DESCR	100	DESCR
HIER_UNIT1_CD	4	F1_EXT_LOOKUP_VALUE
HIER_UNIT1_DESCR	100	DESCR
HIER_UNIT2_CD	4	F1_EXT_LOOKUP_VALUE
HIER_UNIT2_DESCR	100	DESCR
HIER_UNIT3_CD	4	F1_EXT_LOOKUP_VALUE
HIER_UNIT3_DESCR	100	DESCR
UDF1_CD	30	
UDF1_DESCR	60	
UDF2_CD	30	
UDF2_DESCR	60	
UDF3_CD	30	
UDF3_DESCR	60	
UDF4_CD	30	
UDF4_DESCR	60	
UDF5_CD	30	
UDF5_DESCR	60	
UDF6_CD	30	
UDF6_DESCR	60	
UDF7_CD	30	
UDF7_DESCR	60	
UDF8_CD	30	
UDF8_DESCR	60	
UDF9_CD	30	
UDF9_DESCR	60	
UDF10_CD	30	
UDF10_DESCR	60	
DATA_SOURCE_IND	6	Data Source Indicator value in MWM Feature Config

Appointment Time Dimension

This extract program retrieves values from the Extendable Lookup table in the Mobile Workforce Management source system to populate the Appointment Time dimension.

Properties

Property	Value
Load Table Name	CD_APPT_TM
Table Type	Dimension
Source System Driver Table	F1_EXT_LOOKUP_VAL
Source System Extract Program - Initial Load	M1-APTIL
Source System Extract Program - Extract	M1-APTDX
Stage Table Name	STG_APPT_TM_EXT
Stage File Name	D_APPT_TM_EXT.DAT
Control Table Name	STG_APPT_TM_OF_DAY_CTL_EXT
Control File name	D_APPT_TM_OF_DAY_EXT.CTL
Update Procedure Name	SPL_APPT_TM_DEL_PRC
OWB Map Name	SPLMAP_D_ APPT_TM_OF_DAY
OWB Work Flow Name	SPLWF_D_ APPT_TM_OF_DAY
OWB Work Flow Package Name	DIM_MWM

Fields (listed in the order they will appear in the flat file)

Extract Field	Length	Source
UPDATED_DTTM	20	Values: Initial Load: 1/1/2000, Incremental Load: Current Date
CHANGE_TYPE_CD	1	Values: I – Insert/Update, D – Deleted
APPT_TM_CD	30	F1_EXT_LOOKUP_VALUE
APPT_TM_DESCR	100	DESCR
APPT_STATUS_CD	4	FIELD_VALUE
APPT_STATUS_DESCR	100	DESCR
UDF1_CD	30	
UDF1_DESCR	60	
UDF2_CD	30	
UDF2_DESCR	60	

Extract Field	Length	Source
UDF3_CD	30	
UDF3_DESCR	60	
UDF4_CD	30	
UDF4_DESCR	60	
UDF5_CD	30	
UDF5_DESCR	60	
UDF6_CD	30	
UDF6_DESCR	60	
UDF7_CD	30	
UDF7_DESCR	60	
UDF8_CD	30	
UDF8_DESCR	60	
UDF9_CD	30	
UDF9_DESCR	60	
UDF10_CD	30	
UDF10_DESCR	60	
DATA_SOURCE_IND	6	Data Source Indicator value in MWM Feature Config

Appointment Time of Day Dimension

This extract program retrieves values from the Extendable Lookup table in the Mobile Workforce Management source system to populate the Appointment Time of Day dimension.

Properties

Property	Value
Load Table Name	CD_APPT_TM_OF_DAY
Table Type	Dimension
Source System Driver Table	F1_EXT_LOOKUP_VAL
Source System Extract Program - Initial Load	M1-ATDIL
Source System Extract Program - Extract	M1-ATDDX
Stage Table Name	STG_APPT_TM_OF_DAY_EXT
Stage File Name	D_APPT_TM_OF_DAY_EXT.DAT
Control Table Name	STG_APPT_TM_OF_DAY_CTL_EXT

Property	Value
Control File name	D_APPT_TM_OF_DAY_EXT.CTL
Update Procedure Name	SPL_APPT_TM_OF_DAY_DEL_PRC
OWB Map Name	SPLMAP_D_ APPT_TM_OF_DAY
OWB Work Flow Name	SPLWF_D_ APPT_TM_OF_DAY
OWB Work Flow Package Name	DIM_MWM

Fields (listed in the order they will appear in the flat file)

Extract Field	Length	Source
UPDATED_DTTM	20	Values: Initial Load: 1/1/2000, Incremental Load: Current Date
CHANGE_TYPE_CD	1	Values: I – Insert/Update, D – Deleted
APPT_TM_OF_DAY_CD	30	F1_EXT_LOOKUP_VALUE
APPT_TM_OF_DAY_DESCR	100	DESCR
UDF1_CD	30	
UDF1_DESCR	60	
UDF2_CD	30	
UDF2_DESCR	60	
UDF3_CD	30	
UDF3_DESCR	60	
UDF4_CD	30	
UDF4_DESCR	60	
UDF5_CD	30	
UDF5_DESCR	60	
UDF6_CD	30	
UDF6_DESCR	60	
UDF7_CD	30	
UDF7_DESCR	60	
UDF8_CD	30	
UDF8_DESCR	60	
UDF9_CD	30	
UDF9_DESCR	60	
UDF10_CD	30	

Extract Field	Length	Source
UDF10_DESCR	60	
DATA_SOURCE_IND	6	Data Source Indicator value in MWM Feature Config

Travel Duration Deviation Dimension

This extract program retrieves values from the Extendable Lookup table in the Mobile Workforce Management source system to populate the Travel Duration Deviation dimension.

Properties

Property	Value
Load Table Name	CD_TRAVEL_DUR_DEV
Table Type	Dimension
Source System Driver Table	F1_EXT_LOOKUP_VAL
Source System Extract Program - Initial Load	M1-TDDIL
Source System Extract Program - Extract	M1-TDDDX
Stage Table Name	STG_TRAVEL_DUR_DEV_EXT
Stage File Name	D_TRAVEL_DUR_DEV_EXT.DAT
Control Table Name	STG_TRAVEL_DUR_DEV_CTL_EXT
Control File name	D_TRAVEL_DUR_DEV_EXT.CTL
Update Procedure Name	SPL_TRAVEL_DUR_DEV_DEL_PRC
OWB Map Name	SPLMAP_D_ TRAVEL_DUR_DEV
OWB Work Flow Name	SPLWF_D_ TRAVEL_DUR_DEV
OWB Work Flow Package Name	DIM_MWM

Fields (listed in the order they will appear in the flat file)

Extract Field	Length	Source
UPDATED_DTTM	20	Values: Initial Load: 1/1/2000, Incremental Load: Current Date
CHANGE_TYPE_CD	1	Values: I – Insert/Update, D – Deleted
TRAVEL_DUR_DEV_CD	30	F1_EXT_LOOKUP_VALUE
TRAVEL_DUR_DEV_DESCR	100	DESCR
UDF1_CD	30	

Extract Field	Length	Source
UDF1_DESCR	60	
UDF2_CD	30	
UDF2_DESCR	60	
UDF3_CD	30	
UDF3_DESCR	60	
UDF4_CD	30	
UDF4_DESCR	60	
UDF5_CD	30	
UDF5_DESCR	60	
UDF6_CD	30	
UDF6_DESCR	60	
UDF7_CD	30	
UDF7_DESCR	60	
UDF8_CD	30	
UDF8_DESCR	60	
UDF9_CD	30	
UDF9_DESCR	60	
UDF10_CD	30	
UDF10_DESCR	60	
DATA_SOURCE_IND	6	Data Source Indicator value in MWM Feature Config

Late Logon Time Dimension

This extract program retrieves values from the Extendable Lookup table in the Mobile Workforce Management source system to populate the Late Logon Time dimension.

Properties

Property	Value
Load Table Name	CD_LATE_LOGON_TM
Table Type	Dimension
Source System Driver Table	F1_EXT_LOOKUP_VAL
Source System Extract Program - Initial Load	M1-LLTIL
Source System Extract Program - Extract	M1-LLTDX

Property	Value
Stage Table Name	STG_LATE_LOGON_TM_EXT
Stage File Name	D_LATE_LOGON_TM_EXT.DAT
Control Table Name	STG_LATE_LOGON_TM_CTL_EXT
Control File name	D_LATE_LOGON_TM_EXT.CTL
Update Procedure Name	SPL_LATE_LOGON_TM_DEL_PRC
OWB Map Name	SPLMAP_D_LATE_LOGON_TM
OWB Work Flow Name	SPLWF_D_LATE_LOGON_TM
OWB Work Flow Package Name	DIM_MWM

Fields (listed in the order they will appear in the flat file)

Extract Field	Length	Source
UPDATED_DTTM	20	Values: Initial Load: 1/1/2000, Incremental Load: Current Date
CHANGE_TYPE_CD	1	Values: I – Insert/Update, D – Deleted
LATE_LOGON_TM_CD	30	F1_EXT_LOOKUP_VALUE
LATE_LOGON_TM_DESCR	100	DESCR
CONSIDERED_ONTIME_CD	4	FIELD_VALUE
CONSIDERED_ONTIME_DE SCR	100	DESCR
UDF1_CD	30	
UDF1_DESCR	60	
UDF2_CD	30	
UDF2_DESCR	60	
UDF3_CD	30	
UDF3_DESCR	60	
UDF4_CD	30	
UDF4_DESCR	60	
UDF5_CD	30	
UDF5_DESCR	60	
UDF6_CD	30	
UDF6_DESCR	60	
UDF7_CD	30	
UDF7_DESCR	60	

Extract Field	Length	Source
UDF8_CD	30	
UDF8_DESCR	60	
UDF9_CD	30	
UDF9_DESCR	60	
UDF10_CD	30	
UDF10_DESCR	60	
DATA_SOURCE_IND	6	Data Source Indicator value in MWM Feature Config

Early Logoff Time Dimension

This extract program retrieves values from the Extendable Lookup table in the Mobile Workforce Management source system to populate the Early Logoff Time dimension.

Properties

Property	Value
Load Table Name	CD_EARLY_LOGOFF_TM
Table Type	Dimension
Source System Driver Table	F1_EXT_LOOKUP_VAL
Source System Extract Program - Initial Load	M1-ELTIL
Source System Extract Program - Extract	M1-ELTDX
Stage Table Name	STG_EARLY_LOGOFF_TM_EXT
Stage File Name	D_EARLY_LOGOFF_TM_EXT.DAT
Control Table Name	STG_EARLY_LOGOFF_TM_CTL_EXT
Control File name	D_EARLY_LOGOFF_TM_EXT.CTL
Update Procedure Name	SPL_EARLY_LOGOFF_TM_DEL_PRC
OWB Map Name	SPLMAP_D_EARLY_LOGOFF_TM
OWB Work Flow Name	SPLWF_D_EARLY_LOGOFF_TM
OWB Work Flow Package Name	DIM_MWM

Fields (listed in the order they will appear in the flat file)

Extract Field	Length	Source
UPDATED_DTTM	20	Values: Initial Load: 1/1/2000, Incremental Load: Current Date
CHANGE_TYPE_CD	1	Values: I – Insert/Update, D – Deleted
EARLY_LOGOFF_TM_CD		F1_EXT_LOOKUP_VALUE
EARLY_LOGOFF_TM_DESCR		DESCR
CONSIDERED_ONTIME_CD		FIELD_VALUE
CONSIDERED_ONTIME_DESCR		DESCR
UDF1_CD	30	
UDF1_DESCR	60	
UDF2_CD	30	
UDF2_DESCR	60	
UDF3_CD	30	
UDF3_DESCR	60	
UDF4_CD	30	
UDF4_DESCR	60	
UDF5_CD	30	
UDF5_DESCR	60	
UDF6_CD	30	
UDF6_DESCR	60	
UDF7_CD	30	
UDF7_DESCR	60	
UDF8_CD	30	
UDF8_DESCR	60	
UDF9_CD	30	
UDF9_DESCR	60	
UDF10_CD	30	
UDF10_DESCR	60	
DATA_SOURCE_IND	6	Data Source Indicator value in MWM Feature Config

Work Duration Deviation Dimension

This extract program retrieves values from the Extendable Lookup table in the Mobile Workforce Management source system to populate the Work Duration Deviation dimension.

Properties

Property	Value
Load Table Name	CD_WORK_DUR_DEV
Table Type	Dimension
Source System Driver Table	F1_EXT_LOOKUP_VAL
Source System Extract Program - Initial Load	M1-WDDIL
Source System Extract Program - Extract	M1-WDDDX
Stage Table Name	STG_WORK_DUR_DEV_EXT
Stage File Name	D_WORK_DUR_DEV_EXT.DAT
Control Table Name	STG_WORK_DUR_DEV_CTL_EXT
Control File name	D_WORK_DUR_DEV_EXT.CTL
Update Procedure Name	SPL_WORK_DUR_DEV_DEL_PRC
OWB Map Name	SPLMAP_D_ WORK_DUR_DEV
OWB Work Flow Name	SPLWF_D_ WORK_DUR_DEV
OWB Work Flow Package Name	DIM_MWM

Fields (listed in the order they will appear in the flat file)

Extract Field	Length	Source
UPDATED_DTTM	20	Values: Initial Load: 1/1/2000, Incremental Load: Current Date
CHANGE_TYPE_CD	1	Values: I – Insert/Update, D – Deleted
WORK_DUR_DEV_CD	30	F1_EXT_LOOKUP_VALUE
WORK_DUR_DEV_DESCR	100	DESCR
UDF1_CD	30	
UDF1_DESCR	60	
UDF2_CD	30	
UDF2_DESCR	60	
UDF3_CD	30	
UDF3_DESCR	60	
UDF4_CD	30	

Extract Field	Length	Source
UDF4_DESCR	60	
UDF5_CD	30	
UDF5_DESCR	60	
UDF6_CD	30	
UDF6_DESCR	60	
UDF7_CD	30	
UDF7_DESCR	60	
UDF8_CD	30	
UDF8_DESCR	60	
UDF9_CD	30	
UDF9_DESCR	60	
UDF10_CD	30	
UDF10_DESCR	60	
DATA_SOURCE_IND	6	Data Source Indicator value in MWM Feature Config

Travel Distance Deviation Dimension

This extract program retrieves values from the Extendable Lookup table in the Mobile Workforce Management source system to populate the Travel Distance Deviation dimension.

Properties

Property	Value
Load Table Name	CD_TRAVEL_DIST_DEV
Table Type	Dimension
Source System Driver Table	F1_EXT_LOOKUP_VAL
Source System Extract Program - Initial Load	M1-TADIL
Source System Extract Program - Extract	M1-TADDX
Stage Table Name	STG_TRAVEL_DIST_DEV_EXT
Stage File Name	D_TRAVEL_DIST_DEV_EXT.DAT
Control Table Name	STG_TRAVEL_DIST_DEV_CTL_EXT
Control File name	D_TRAVEL_DIST_DEV_EXT.CTL
Update Procedure Name	SPL_TRAVEL_DIST_DEV_DEL_PRC
OWB Map Name	SPLMAP_D_TRAVEL_DIST_DEV

Property	Value
OWB Work Flow Name	SPLWF_D_TRAVEL_DIST_DEV
OWB Work Flow Package Name	DIM_MWM

Fields (listed in the order they will appear in the flat file)

Extract Field	Length	Source
UPDATED_DTTM	20	Values: Initial Load: 1/1/2000, Incremental Load: Current Date
CHANGE_TYPE_CD	1	Values: I – Insert/Update, D – Deleted
TRAVEL_DIST_DEV_CD	30	F1_EXT_LOOKUP_VALUE
TRAVEL_DIST_DEV_DESCR	100	DESCR
UDF1_CD	30	
UDF1_DESCR	60	
UDF2_CD	30	
UDF2_DESCR	60	
UDF3_CD	30	
UDF3_DESCR	60	
UDF4_CD	30	
UDF4_DESCR	60	
UDF5_CD	30	
UDF5_DESCR	60	
UDF6_CD	30	
UDF6_DESCR	60	
UDF7_CD	30	
UDF7_DESCR	60	
UDF8_CD	30	
UDF8_DESCR	60	
UDF9_CD	30	
UDF9_DESCR	60	
UDF10_CD	30	
UDF10_DESCR	60	
DATA_SOURCE_IND	6	Data Source Indicator value in MWM Feature Config

Response Time Deviation Dimension

This extract program retrieves values from the Extendable Lookup table in the Mobile Workforce Management source system to populate the Response Time Deviation dimension.

Properties

Property	Value
Load Table Name	CD_RESP_TM_DEV
Table Type	Dimension
Source System Driver Table	F1_EXT_LOOKUP_VAL
Source System Extract Program - Initial Load	M1-RTDIL
Source System Extract Program - Extract	M1-RTDDX
Stage Table Name	STG_RESP_TM_DEV_EXT
Stage File Name	D_RESP_TM_DEV_EXT.DAT
Control Table Name	STG_RESP_TM_DEV_CTL_EXT
Control File name	D_RESP_TM_DEV_EXT.CTL
Update Procedure Name	SPLMAP_D_RESP_TM_DEV
OWB Map Name	SPL_RESP_TM_DEV_DEL_PRC
OWB Work Flow Name	SPLWF_D_RESP_TM_DEV
OWB Work Flow Package Name	DIM_MWM

Fields (listed in the order they will appear in the flat file)

Extract Field	Length	Source
UPDATED_DTTM	20	Values: Initial Load: 1/1/2000, Incremental Load: Current Date
CHANGE_TYPE_CD	1	Values: I – Insert/Update, D – Deleted
RESP_TM_DEV_CD	30	F1_EXT_LOOKUP_VALUE
RESP_TM_DEV_DESCR	100	DESCR
SLA_STATE_CD	4	FIELD_VALUE
SLA_STATE_DESCR	100	DESCR
UDF1_CD	30	
UDF1_DESCR	60	
UDF2_CD	30	
UDF2_DESCR	60	
UDF3_CD	30	

Extract Field	Length	Source
UDF3_DESCR	60	
UDF4_CD	30	
UDF4_DESCR	60	
UDF5_CD	30	
UDF5_DESCR	60	
UDF6_CD	30	
UDF6_DESCR	60	
UDF7_CD	30	
UDF7_DESCR	60	
UDF8_CD	30	
UDF8_DESCR	60	
UDF9_CD	30	
UDF9_DESCR	60	
UDF10_CD	30	
UDF10_DESCR	60	
DATA_SOURCE_IND	6	Data Source Indicator value in MWM Feature Config

Address Dimension

This extract program retrieves values from the Task Address table in the Mobile Workforce Management source system to populate the Address dimension.

Properties

Property	Value
Load Table Name	CD_ADDR
Table Type	Dimension
Source System Driver Table	M1_TASK_ADDR
Source System Extract Program - Initial Load	M1-LOCIL,M1-CSAIL,M1-TKAIL
Source System Extract Program - Extract	M1-ADRDX
Stage Table Name	STG_ADDR_EXT
Stage File Name	D_ADDR_EXT.DAT
Control Table Name	STG_ADDR_CTL_EXT
Control File name	D_ADDR_EXT.CTL

Property	Value
Update Procedure Name	SPL_ADDR_UPD_PRC
OWB Map Name	SPLMAP_D_ ADDR
OWB Work Flow Name	SPLWF_D_ ADDR
OWB Work Flow Package Name	DIM

Fields (listed in the order they will appear in the flat file)

Extract Field	Length	Source
UPDATED_DTTM	20	Values: Initial Load: 1/1/2000, Incremental Load: Current Date
CHANGE_TYPE_CD	1	Values: I – Insert/Update, D – Deleted
SRC_ADDR_ID	254	SRC_ADDR_ID
ADDRESS_LINE1	254	ADDRESS1
ADDRESS_LINE2	254	ADDRESS2
ADDRESS_LINE3	254	ADDRESS3
ADDRESS_LINE4	254	ADDRESS4
CROSS_STREET	100	CROSS_STREET
SUBURB	100	SUBURB
CITY	60	CITY
COUNTY	60	COUNTY
POSTAL	12	POSTAL
STATE_CD	6	STATE
STATE_DESCR	100	DESCR
COUNTRY_CD	3	COUNTRY
COUNTRY_DESCR	100	DESCR
GEO_CD	11	GEO_CODE
UDF1_CD	30	
UDF1_DESCR	60	
UDF2_CD	30	
UDF2_DESCR	60	
UDF3_CD	30	
UDF3_DESCR	60	
UDF4_CD	30	

Extract Field	Length	Source
UDF4_DESCR	60	
UDF5_CD	30	
UDF5_DESCR	60	
UDF6_CD	30	
UDF6_DESCR	60	
UDF7_CD	30	
UDF7_DESCR	60	
UDF8_CD	30	
UDF8_DESCR	60	
UDF9_CD	30	
UDF9_DESCR	60	
UDF10_CD	30	
UDF10_DESCR	60	
ADDR_INFO	254	ADDRESS1+CITY+STATE+POSTAL
DATA_SOURCE_IND	6	Data Source Indicator value in MWM Feature Config

Fact Extract Programs

Crew Tasks Fact

This extract program retrieves values from the Task Schedule table in the Mobile Workforce Management source system to populate the Crew Tasks fact.

Properties

Property	Value
Load Table Name	CF_CREW_TASK
Table Type	Fact
Source System Driver Table	M1_TASK_SCHEDULE
Source System Extract Program - Initial Load	M1-SFTIL
Source System Extract Program - Extract	M1-CRTFX
Stage Table Name	STG_CREW_TASK_EXT
Stage File Name	F_CREW_TASK_EXT.DAT
Control Table Name	STG_CREW_TASK_CTL_EXT
Control File name	F_CREW_TASK_EXT.CTL
Update Procedure Name	
OWB Map Name	SPLMAP_F_CREW_TASK
OWB Work Flow Name	SPLWF_F_CREW_TASK
OWB Work Flow Package Name	FACT_MWM

Fields (listed in the order they will appear in the flat file)

Extract Field	Length	Source
UPDATED_DTTM	20	Values: Initial Load: 1/1/2000, Incremental Load: Current Date
CHANGE_TYPE_CD	1	Values: I – Insert/Update, D – Deleted
SHIFT_ID	30	SHIFT_ID
TASK_ID	30	TASK_ID
SHIFT_LOG_SEQUENCE	10	SEQNO
TASK_LOG_SEQUENCE	10	SEQNO
TIME_IN_PREVIOUS_STATE	15	TIME_IN_PREVIOUS_STATE
APPOINTMENT_IND	1	APPOINTMENT_FLG
ENERGENCY_IND	1	QUEUE_FLG

Extract Field	Length	Source
ESTIMATED_TRAVEL_TIME	15	Stage: ESTIMATED_TRAVEL_TIME
CREW_TIME_USAGE_CD	30	F1_EXT_LOOKUP_VAL. F1_EXT_LOOKUP_VALUE
FROM_SHIFT_BO_CD	30	F1_BUS_OBJ.BUS_OBJ_CD
FROM_BO_STATUS_CD	12	F1_BUS_OBJ_STATUS.BO_STATUS_CD
FROM_STATUS_REASON_CD	30	F1_BUS_OBJ_STATUS_RSN.BO_STATUS_REASON_CD
TO_SHIFT_BO_CD	30	F1_BUS_OBJ.BUS_OBJ_CD
TO_BO_STATUS_CD	12	F1_BUS_OBJ_STATUS.BO_STATUS_CD
TO_STATUS_REASON_CD	30	F1_BUS_OBJ_STATUS_RSN.BO_STATUS_REASON_CD
CREW_CD	30	M1_RESRC.RESRC_ID
TRAVEL_DURATION_DEVIATION_CD	30	F1_EXT_LOOKUP_VAL. F1_EXT_LOOKUP_VALUE
APPOINTMENT_TIME_OF_DAY_CD	30	F1_EXT_LOOKUP_VAL. F1_EXT_LOOKUP_VALUE
APPOINTMENT_TIME_CD	30	F1_EXT_LOOKUP_VAL. F1_EXT_LOOKUP_VALUE
FROM_TASK_BO_CD	30	F1_BUS_OBJ.BUS_OBJ_CD
FROM_BO_STATUS_CD	12	F1_BUS_OBJ_STATUS.BO_STATUS_CD
FROM_STATUS_REASON_CD	30	F1_BUS_OBJ_STATUS_RSN.BO_STATUS_REASON_CD
TO_TASK_BO_CD	30	F1_BUS_OBJ.BUS_OBJ_CD
TO_BO_STATUS_CD	12	F1_BUS_OBJ_STATUS.BO_STATUS_CD
TO_STATUS_REASON_CD	30	F1_BUS_OBJ_STATUS_RSN.BO_STATUS_REASON_CD
TASK_TYPE_CD	30	M1_TASK_TYPE.TASK_TYPE_CD
SERVICE_AREA_CD	30	M1_SVC_AREA.SVC_AREA_CD
ADDRESS_ID	254	M1_TASK_ADDRESS(ADDRESS1+CITY+STATE+POSTAL)
FROM_DATE	8	Stage: FROM_DATE
FROM_TIME	8	Stage: FROM_TIME
FROM_DTTM	20	Stage: FROM_DTTM
TO_DATE	8	Stage: TO_DATE
TO_TIME	8	Stage: TO_TIME
TO_DTTM	20	Stage: TO_DTTM

Extract Field	Length	Source
DEVICE_ID	30	D1_DVC.D1_DEVICE_ID
SERVICE_POINT_ID	30	D1_SP.D1_SP_ID
USG_SUBSCRIPTION_ID	30	D1_US.US_ID
CONTACT_ID	30	D1_CONTACT.CONTACT_ID
PERSON_ID	30	
ACCOUNT_ID	30	
SA_ID	30	
PREMISE_ID	30	
UDD1_CD	16	Stage: UDD1_CD
UDD2_CD	16	Stage: UDD2_CD
UDM1	19	Stage: UDM1
UDM2	19	Stage: UDM2
UDM3	19	Stage: UDM3
UDM4	19	Stage: UDM4
UDM5	19	Stage: UDM5
UDM6	19	Stage: UDM6
UDM7	19	Stage: UDM7
UDM8	19	Stage: UDM8
UDM9	19	Stage: UDM9
UDM10	19	Stage: UDM10
UDDGEN1	8	Stage: UDDGEN1
UDDGEN2	8	Stage: UDDGEN2
UDDGEN3	8	Stage: UDDGEN3
UDDGEN4	8	Stage: UDDGEN4
UDDGEN5	8	Stage: UDDGEN5
UDDGENL1	30	Stage: UDDGENL1
UDDGENL2	30	Stage: UDDGENL2
UDDGENL3	30	Stage: UDDGENL3
UDDGENL4	30	Stage: UDDGENL4
UDDGENL5	30	Stage: UDDGENL5
UDDFK1_KEY	254	Stage: UDDFK1_KEY
UDDFK2_KEY	254	Stage: UDDFK2_KEY
UDDFK3_KEY	254	Stage: UDDFK3_KEY

Extract Field	Length	Source
UDDFK4_KEY	254	Stage: UDDFK4_KEY
UDDFK5_KEY	254	Stage: UDDFK5_KEY
DATA_SOURCE_IND	6	Data Source Indicator value in MWM Feature Config

Completed Shift Fact

This extract program retrieves values from the Crew Shift table in the Mobile Workforce Management source system to populate the Completed Shift fact.

Properties

Property	Value
Load Table Name	CF_CMP_SHIFT
Table Type	Fact
Source System Driver Table	M1_CREW_SHIFT
Source System Extract Program - Initial Load	M1-SFTIL
Source System Extract Program - Extract	M1-CCSFX
Stage Table Name	STG_CMP_SHIFT_EXT
Stage File Name	F_CMP_SHIFT_EXT.DAT
Control Table Name	STG_CMP_SHIFT_CTL_EXT
Control File name	F_CMP_SHIFT_EXT.CTL
Update Procedure Name	
OWB Map Name	SPLMAP_F_CMP_SHIFT
OWB Work Flow Name	SPLWF_F_CMP_SHIFT
OWB Work Flow Package Name	FACT_MWM

Fields (listed in the order they will appear in the flat file)

Extract Field	Length	Source
UPDATED_DTTM	20	Values: Initial Load: 1/1/2000, Incremental Load: Current Date
CHANGE_TYPE_CD	1	Values: I – Insert/Update, D – Deleted
SHIFT_ID	30	SHIFT_ID
PLANNED_DURATION	15	Stage: PLANNED_DURATION

Extract Field	Length	Source
ACTUAL_DURATION	15	Stage: ACTUAL_DURATION
OVERTIME_DURATION		Stage: OVERTIME_DURATION
ESTIMATED_DISTANCE		Stage: ESTIMATED_DISTANCE
EST_TOT_MILEAGE		Stage: EST_TOT_MILEAGE
ACTUAL_TOT_MILEAGE		Stage: ACTUAL_TOT_MILEAGE
VEHICLE_CNT		Stage: VEHICLE_CNT
CREW_CD		M1_RESRC.RESRC_ID
LATE_LOGON_TIME_CD		F1_EXT_LOOKUP_VAL. F1_EXT_LOOKUP_VALUE
EARLY_LOGOFF_TIME_CD		F1_EXT_LOOKUP_VAL. F1_EXT_LOOKUP_VALUE
TRAVEL_DIST_DEV_CD		F1_EXT_LOOKUP_VAL. F1_EXT_LOOKUP_VALUE
LOGON_ADDRESS_ID		M1_TASK_ADDRESS(ADDRESS1+CITY+STATE+POSTAL)
LOGOFF_ADDRESS_ID		M1_TASK_ADDRESS(ADDRESS1+CITY+STATE+POSTAL)
SHIFT_PLAN_ST_DATE		Stage: SHIFT_PLAN_ST_DATE
SHIFT_PLAN_ST_TIME		Stage: SHIFT_PLAN_ST_TIME
SHIFT_PLAN_ST_DT		Stage: SHIFT_PLAN_ST_DT
UDD1_CD	16	Stage: UDD1_CD
UDD2_CD	16	Stage: UDD2_CD
UDM1	19	Stage: UDM1
UDM2	19	Stage: UDM2
UDM3	19	Stage: UDM3
UDM4	19	Stage: UDM4
UDM5	19	Stage: UDM5
UDM6	19	Stage: UDM6
UDM7	19	Stage: UDM7
UDM8	19	Stage: UDM8
UDM9	19	Stage: UDM9
UDM10	19	Stage: UDM10
UDDD1	8	Stage: UDDD1
UDDD2	8	Stage: UDDD2
UDDD3	8	Stage: UDDD3

Extract Field	Length	Source
UDDD4	8	Stage: UDDD4
UDDD5	8	Stage: UDDD5
UDLDD1	30	Stage: UDLDD1
UDLDD2	30	Stage: UDLDD2
UDLDD3	30	Stage: UDLDD3
UDLDD4	30	Stage: UDLDD4
UDLDD5	30	Stage: UDLDD5
UDDFK_ID1	254	Stage: UDDFK_ID1
UDDFK_ID2	254	Stage: UDDFK_ID2
UDDFK_ID3	254	Stage: UDDFK_ID3
UDDFK_ID4	254	Stage: UDDFK_ID4
UDDFK_ID5	254	Stage: UDDFK_ID5
DATA_SOURCE_IND	6	Data Source Indicator value in MWM Feature Config

Activity Fact

This extract program retrieves values from the Task table in the Mobile Workforce Management source system to populate the Activity fact.

Properties

Property	Value
Load Table Name	CF_FLD_ACTIVITY
Table Type	Fact
Source System Driver Table	M1_TASK
Source System Extract Program - Initial Load	M1-ACTIL
Source System Extract Program - Extract	M1-ACTFX
Stage Table Name	STG_FLD_ACTIVITY_EXT
Stage File Name	F_FLD_ACTIVITY_EXT.DAT
Control Table Name	STG_FLD_ACTIVITY_CTL_EXT
Control File name	F_FLD_ACTIVITY_EXT.CTL
Update Procedure Name	
OWB Map Name	SPLMAP_F_FLD_ACTIVITY
OWB Work Flow Name	SPLWF_F_FLD_ACTIVITY

Property	Value
OWB Work Flow Package Name	FACT_MWM

Fields (listed in the order they will appear in the flat file)

Extract Field	Length	Source
UPDATED_DT_TM	20	Values: Initial Load: 1/1/2000, Incremental Load: Current Date
CHANGE_TYPE_CD	1	Values: I – Insert/Update, D – Deleted
TASK_ID	30	M1_TASK.TASK_ID
TASK_INFO	254	
EMERGENCY_INDICATOR	1	M1_TASK.QUEUE_FLG
APPOINTMENT_IND	1	M1_TASK.APPOINTMENT_FLG
SAME_DAY_APPT_IND	1	Stage: SAME_DAY_APPT_IND
WORK_DUR	15	Stage: WORK_DUR
EST_WORK_DUR	15	Stage: EST_WORK_DUR
ACTUAL_WORK_DUR	15	Stage: ACTUAL_WORK_DUR
ACTUAL_TRAVEL_DUR	15	Stage: ACTUAL_TRAVEL_DUR
WORK_ATTEMPTS	15	Stage: WORK_ATTEMPTS
TRAVEL_ATTEMPTS	15	Stage: TRAVEL_ATTEMPTS
RESPONSE_TIME_UNTIL_DISP	15	Stage: RESPONSE_TIME_UNTIL_DISP
RESPONSE_TIME_UNTIL_ENRO	15	Stage: RESPONSE_TIME_UNTIL_ENRO
RESPONSE_TIME_UNTIL_ARRIVED	15	Stage: RESPONSE_TIME_UNTIL_ARRIVED
RESPONSE_TIME_UNTIL_COMPLETED	15	Stage: RESPONSE_TIME_UNTIL_COMPLETED
OVERALL_RESPONSE_TIME	15	Stage: OVERALL_RESPONSE_TIME
TASK_BO_CD	30	F1_BUS_OBJ.BUS_OBJ_CD
BO_STATUS_CD	12	F1_BUS_OBJ.STATUS.BO_STATUS_CD
STATUS_REASON_CD	30	F1_BUS_OBJ.STATUS_RSN.BO_STATUS_REASON_CD
TASK_TYPE_CD	30	M1_TASK_TYPE.TASK_TYPE_CD
SERVICE_AREA_CD	30	M1_SVC_AREA.SVC_AREA_CD
ADDRESS_ID	254	M1_TASK_ADDRESS(ADDRESS1+CITY+STATE+POSTAL)
CREW_CD	30	M1_RESRC.RESRC_ID

Extract Field	Length	Source
APPOINTMENT_TIME_DAY_CD	30	F1_EXT_LOOKUP_VAL. F1_EXT_LOOKUP_VALUE
APPOINTMENT_TIME_CD	30	F1_EXT_LOOKUP_VAL. F1_EXT_LOOKUP_VALUE
WRL_DUR_DEV_CD	30	F1_EXT_LOOKUP_VAL. F1_EXT_LOOKUP_VALUE
RESPONSE_TIME_DEV_CD	30	F1_EXT_LOOKUP_VAL. F1_EXT_LOOKUP_VALUE
CREATION_DATE	8	Stage: CREATION_DATE
CREATION_TIME	8	Stage: CREATION_TIME
CREATION_DATETIME	20	Stage: CREATION_DATETIME
STATUS_DATE	8	Stage: STATUS_DATE
STATUS_TIME	8	Stage: STATUS_TIME
STATUS_DATETIME	20	Stage: STATUS_DATETIME
SCHEDULE_START_DATE	8	Stage: SCHEDULE_START_DATE
SCHEDULE_START_TIME	8	Stage: SCHEDULE_START_TIME
SCHEDULE_START_DATETIME	20	Stage: SCHEDULE_START_DATETIME
SCHEDULE_END_DATE	8	Stage: SCHEDULE_END_DATE
SCHEDULE_END_TIME	8	Stage: SCHEDULE_END_TIME
SCHEDULE_END_DATETIME	20	Stage: SCHEDULE_END_DATETIME
DEVICE_ID	30	D1_DVC.D1_DEVICE_ID
SERVICE_POINT_ID	30	D1_SP.D1_SP_ID
USAGE_SUBSCRIPT_ID	30	D1_US.US_ID
CONTACT_ID	30	D1_CONTACT.CONTACT_ID
PERSON_ID	30	CI_PER.PER_ID
ACCOUNT_ID	30	CI_ACCT.ACCT_ID
SA_ID	30	CI_SA.SA_ID
PREMISE_ID	30	CI_PREM.PREM_ID
UDD1_CD	16	Stage: UDD1_CD
UDD2_CD	16	Stage: UDD2_CD
UDM1	19	Stage: UDM1
UDM2	19	Stage: UDM2
UDM3	19	Stage: UDM3

Extract Field	Length	Source
UDM4	19	Stage: UDM4
UDM5	19	Stage: UDM5
UDM6	19	Stage: UDM6
UDM7	19	Stage: UDM7
UDM8	19	Stage: UDM8
UDM9	19	Stage: UDM9
UDM10	19	Stage: UDM10
UDDD1	8	Stage: UDDD1
UDDD2	8	Stage: UDDD2
UDDD3	8	Stage: UDDD3
UDDD4	8	Stage: UDDD4
UDDD5	8	Stage: UDDD5
UDLDD1	30	Stage: UDLDD1
UDLDD2	30	Stage: UDLDD2
UDLDD3	30	Stage: UDLDD3
UDLDD4	30	Stage: UDLDD4
UDLDD5	30	Stage: UDLDD5
UDDFK_ID1	254	Stage: UDDFK_ID1
UDDFK_ID2	254	Stage: UDDFK_ID2
UDDFK_ID3	254	Stage: UDDFK_ID3
UDDFK_ID4	254	Stage: UDDFK_ID4
UDDFK_ID5	254	Stage: UDDFK_ID5
DATA_SOURCE_IND	6	Data Source Indicator value in MWM Feature Config

Dimension Table Schema

Crew Time Usage Dimension <CD_CREW_TM_USG>

The Crew Time Usage dimension stores various crew time usage types that indicate different states in which a crew can exist.

Properties

Property	Value
Table Type	Dimension
SCD Type	1

Fields

Column	OBIEE Field	Load
CREW_TM_USG_KEY	Crew Time Usage Dimension Surrogate Key	Sequence: OUBL_CREW_TM_USG_SEQ
CREW_TM_USG_CD	Crew Time Usage Code	CREW_TM_USG_CD
CREW_TM_USG_DESCR	Crew Time Usage Description	CREW_TM_USG_DESCR
PRODUCTIVITY_CD	Productivity Code	PRODUCTIVITY_CD
PRODUCTIVITY_DESCR	Productivity Description	Stage: PRODUCTIVITY_DESCR
UDF1_CD	User Defined Field Code	Stage: UDF1_CD
UDF1_DESCR	User Defined Field Code	Stage: UDF1_DESCR
UDF2_CD	User Defined Field Code	Stage: UDF2_CD
UDF2_DESCR	User Defined Field Code	Stage: UDF2_DESCR
UDF3_CD	User Defined Field Code	Stage: UDF3_CD
UDF3_DESCR	User Defined Field Code	Stage: UDF3_DESCR
UDF4_CD	User Defined Field Code	Stage: UDF4_CD
UDF4_DESCR	User Defined Field Code	Stage: UDF4_DESCR
UDF5_CD	User Defined Field Code	Stage: UDF5_CD
UDF5_DESCR	User Defined Field Code	Stage: UDF5_DESCR
UDF6_CD	User Defined Field Code	Stage: UDF6_CD
UDF6_DESCR	User Defined Field Code	Stage: UDF6_DESCR
UDF7_CD	User Defined Field Code	Stage: UDF7_CD

Column	OBIEE Field	Load
UDF7_DESCR	User Defined Field Code	Stage: UDF7_DESCR
UDF8_CD	User Defined Field Code	Stage: UDF8_CD
UDF8_DESCR	User Defined Field Code	Stage: UDF8_DESCR
UDF9_CD	User Defined Field Code	Stage: UDF9_CD
UDF9_DESCR	User Defined Field Code	Stage: UDF9_DESCR
UDF10_CD	User Defined Field Code	Stage: UDF10_CD
UDF10_DESCR	User Defined Field Code	Stage: UDF10_DESCR
UPDATE_DTTM	Update Date/Time	Stage: UPDATED_DATE_TIME
DATA_LOAD_DTTM	Data Load Date/Time	System Variable: CURRENT_DATE
DATA_SOURCE_IND	Data Source Indicator	Stage: DATA_SOURCE_IND
JOB_NBR	Job Number	Job Control: JOB_NBR

Shift Business Object Status Dimension <CD_SHIFT_BO_STATUS>

The Shift Business Object (BO) Status dimension stores the shift BO status information and holds a row for every combination of BO/Status/Reason for the Crew Shift BOs.

Properties

Property	Value
Table Type	Dimension
SCD Type	1

Fields

Column	OBIEE Field	Load
SHIFT_BO_STATUS_KEY	Shift Bo Status Surrogate Key	Sequence: OUBL_SHIFT_BO_STAT_S EQ
BUS_OBJ_CD	Business Object Code	Stage: BUS_OBJ_CD
BUS_OBJ_DESCR	Bo Description	Stage: BUS_OBJ_DESCR
STATUS_CD	Bo Status Code	Stage: STATUS_CD
STATUS_DESCR	Status Description	Stage: STATUS_DESCR
STATUS_COND_CD	Status Condition Code	Stage: STATUS_COND_CD

STATUS_COND_DESCR	Status Condition Description	Stage: STATUS_COND_DESCR
REASON_CD	Status Reason Code	Stage: REASON_CD
REASON_DESCR	Status Reason Description	Stage: REASON_DESCR
UDF1_CD	User Defined Field Code	Stage: UDF1_CD
UDF1_DESCR	User Defined Field Description	Stage: UDF1_DESC
UDF2_CD	User Defined Field Code	Stage: UDF2_CD
UDF2_DESCR	User Defined Field Description	Stage: UDF2_DESC
UDF3_CD	User Defined Field Code	Stage: UDF3_CD
UDF3_DESCR	User Defined Field Description	Stage: UDF3_DESC
UDF4_CD	User Defined Field Code	Stage: UDF4_CD
UDF4_DESCR	User Defined Field Description	Stage: UDF4_DESC
UDF5_CD	User Defined Field Code	Stage: UDF5_CD
UDF5_DESCR	User Defined Field Description	Stage: UDF5_DESC
UDF6_CD	User Defined Field Code	Stage: UDF6_CD
UDF6_DESCR	User Defined Field Description	Stage: UDF6_DESC
UDF7_CD	User Defined Field Code	Stage: UDF7_CD
UDF7_DESCR	User Defined Field Description	Stage: UDF7_DESC
UDF8_CD	User Defined Field Code	Stage: UDF8_CD
UDF8_DESCR	User Defined Field Description	Stage: UDF8_DESC
UDF9_CD	User Defined Field Code	Stage: UDF9_CD
UDF9_DESCR	User Defined Field Description	Stage: UDF9_DESC
UDF10_CD	User Defined Field Code	Stage: UDF10_CD
UDF10_DESCR	User Defined Field Description	Stage: UDF10_DESC
UPDATE_DTTM	Update Date/Time	Stage: UPDATED_DATE_TIME

DATA_LOAD_DTTM	Data Load Date/Time	System Variable: CURRENT_DATE
DATA_SOURCE_IND	Data Source Indicator	Stage: DATA_SOURCE_IND
JOB_NBR	Job Number	Job Control: JOB_NBR

Task Business Object Status Dimension <CD_TASK_BO_STATUS>

The Task Business Object (BO) Status dimension stores the shift BO status information and holds a row for every combination of BO/Status/Reason for schedulable Task BOs.

Properties

Property	Value
Table Type	Dimension
SCD Type	1

Fields

Column	OBIEE Field	Load
TASK_BO_STATUS_KEY	Task Bo Status Surrogate Key	Sequence: OUBI_TASK_BO_STAT_SE Q
BUS_OBJ_CD	Business Object Code	Stage: BUS_OBJ_CD
BUS_OBJ_DESCR	Bo Description	Stage: BUS_OBJ_DESCR
STATUS_CD	Bo Status Code	Stage: STATUS_CD
STATUS_DESCR	Status Description	Stage: STATUS_DESCR
STATUS_COND_CD	Status Condition Code	Stage: STATUS_COND_CD
STATUS_COND_DESCR	Status Condition Description	Stage: STATUS_COND_DESCR
REASON_CD	Status Reason Code	Stage: REASON_CD
REASON_DESCR	Status Reason Description	Stage: REASON_DESCR
INCOMPLETE_IND	Incomplete Indicator	Stage: IINCOMPLETE_IND
UDF1_CD	User Defined Field Code	Stage: UDF1_CD
UDF1_DESCR	User Defined Field Description	Stage: UDF1_DESC

UDF2_CD	User Defined Field Code	Stage: UDF2_CD
UDF2_DESCR	User Defined Field Description	Stage: UDF2_DESC
UDF3_CD	User Defined Field Code	Stage: UDF3_CD
UDF3_DESCR	User Defined Field Description	Stage: UDF3_DESC
UDF4_CD	User Defined Field Code	Stage: UDF4_CD
UDF4_DESCR	User Defined Field Description	Stage: UDF4_DESC
UDF5_CD	User Defined Field Code	Stage: UDF5_CD
UDF5_DESCR	User Defined Field Description	Stage: UDF5_DESC
UDF6_CD	User Defined Field Code	Stage: UDF6_CD
UDF6_DESCR	User Defined Field Description	Stage: UDF6_DESC
UDF7_CD	User Defined Field Code	Stage: UDF7_CD
UDF7_DESCR	User Defined Field Description	Stage: UDF7_DESC
UDF8_CD	User Defined Field Code	Stage: UDF8_CD
UDF8_DESCR	User Defined Field Description	Stage: UDF8_DESC
UDF9_CD	User Defined Field Code	Stage: UDF9_CD
UDF9_DESCR	User Defined Field Description	Stage: UDF9_DESC
UDF10_CD	User Defined Field Code	Stage: UDF10_CD
UDF10_DESCR	User Defined Field Description	Stage: UDF10_DESC
UPDATE_DTTM	Update Date/Time	Stage: UPDATED_DATE_TIME
DATA_LOAD_DTTM	Data Load Date/Time	System Variable: CURRENT_DATE
DATA_SOURCE_IND	Data Source Indicator	Stage: DATA_SOURCE_IND
JOB_NBR	Job Number	Job Control: JOB_NBR

Crew Shift Dimension <CD_CREW_SHIFT>

The Crew Shift dimension stores shift details of the respective crew.

Properties

Property	Value
Table Type	Dimension
SCD Type	2

Fields

Column	OBIEE Field	Load
CREW_SHIFT_KEY	Crew shift key	Stage: CREW_SHIFT_KEY
DATA_LOAD_DTTM	Data Load Date/Time	System Variable: CURRENT_DATE
DATA_SOURCE_IND	Data Source Indicator	Stage: DATA_SOURCE_IND
EFF_START_DTTM	Effective Start Date/Time	UPDATE_DTTM
EFF_END_DTTM	Effective End Date/Time	System Variable: HIGH_DATE
JOB_NBR	Job Number	Job Control: JOB_NBR
SRC_CREW_SHIFT_ID	Crew Shift ID	Stage: CREW_SHIFT_ID
UDF1_CD	User Defined Field Code	Stage: UDF1_CD
UDF1_DESCR	User Defined Field Description	Stage: UDF1_DESC
UDF2_CD	User Defined Field Code	Stage: UDF2_CD
UDF2_DESCR	User Defined Field Description	Stage: UDF2_DESC
UDF3_CD	User Defined Field Code	Stage: UDF3_CD
UDF3_DESCR	User Defined Field Description	Stage: UDF3_DESC
UDF4_CD	User Defined Field Code	Stage: UDF4_CD
UDF4_DESCR	User Defined Field Description	Stage: UDF4_DESC
UDF5_CD	User Defined Field Code	Stage: UDF5_CD
UDF5_DESCR	User Defined Field Description	Stage: UDF5_DESC

UDF6_CD	User Defined Field Code	Stage: UDF6_CD
UDF6_DESCR	User Defined Field Description	Stage: UDF6_DESC
UDF7_CD	User Defined Field Code	Stage: UDF7_CD
UDF7_DESCR	User Defined Field Description	Stage: UDF7_DESC
UDF8_CD	User Defined Field Code	Stage: UDF8_CD
UDF8_DESCR	User Defined Field Description	Stage: UDF8_DESC
UDF9_CD	User Defined Field Code	Stage: UDF9_CD
UDF9_DESCR	User Defined Field Description	Stage: UDF9_DESC
UDF10_CD	User Defined Field Code	Stage: UDF10_CD
UDF10_DESCR	User Defined Field Description	Stage: UDF10_DESC
CREW_SHIFT_INFO	Shift Description	Stage: SHIFT_INFO
CREW_SHIFT_TYPE_CD	Shift Type Code	Stage: CREW_SHIFT_TYPE_CD
CREW_SHIFT_TYPE_DESCR	Shift Type Description	Stage: CREW_SHIFT_TYPE_DESCR
PRIMARY_FN_CD	Primary Function Code	Stage: PRIMARY_FN_CD
PRIMARY_FN_DESCR	Primary Function Description	Stage: PRIMARY_FN_DESCR

Crew Dimension <CD_CREW>

The Crew dimension stores resource information for a crew.

Properties

Property	Value
Table Type	Dimension
SCD Type	2

Fields

Column	OBIEE Field	Load
--------	-------------	------

CREW_CD	Crew Code	Stage: CREW_CD
CREW_TYPE_CD	Crew Type Code	Stage: CREW_TYPE_CD
CREW_TYPE_DESCR	Crew Type Description	Stage: CREW_TYPE_DESCR
ORG_UNIT1_CD	Organization Unit 1 Code	Stage: ORG_UNIT1_CD
ORG_UNIT1_DESCR	Organization Unit 1 Description	Stage: ORG_UNIT1_DESCR
ORG_UNIT2_CD	Organization Unit 2 Code	Stage: ORG_UNIT2_CD
ORG_UNIT2_DESCR	Organization Unit 2 Description	Stage: ORG_UNIT2_DESCR
ORG_UNIT3_CD	Organization Unit 3 Code	Stage: ORG_UNIT3_CD
ORG_UNIT3_DESCR	Organization Unit 3 Description	Stage: ORG_UNIT3_DESCR
SRC_CREW_ID	Crew ID	Stage: CREW_ID
UDF1_CD	User Defined Field Code	Stage: UDF1_CD
UDF1_DESCR	User Defined Field Description	Stage: UDF1_DESC
UDF2_CD	User Defined Field Code	Stage: UDF2_CD
UDF2_DESCR	User Defined Field Description	Stage: UDF2_DESC
UDF3_CD	User Defined Field Code	Stage: UDF3_CD
UDF3_DESCR	User Defined Field Description	Stage: UDF3_DESC
UDF4_CD	User Defined Field Code	Stage: UDF4_CD
UDF4_DESCR	User Defined Field Description	Stage: UDF4_DESC
UDF5_CD	User Defined Field Code	Stage: UDF5_CD
UDF5_DESCR	User Defined Field Description	Stage: UDF5_DESC
UDF6_CD	User Defined Field Code	Stage: UDF6_CD
UDF6_DESCR	User Defined Field Description	Stage: UDF6_DESC
UDF7_CD	User Defined Field Code	Stage: UDF7_CD
UDF7_DESCR	User Defined Field Description	Stage: UDF7_DESC
UDF8_CD	User Defined Field Code	Stage: UDF8_CD

UDF8_DESCR	User Defined Field Description	Stage: UDF8_DESC
UDF9_CD	User Defined Field Code	Stage: UDF9_CD
UDF9_DESCR	User Defined Field Description	Stage: UDF9_DESC
UDF10_CD	User Defined Field Code	Stage: UDF10_CD
UDF10_DESCR	User Defined Field Description	Stage: UDF10_DESC
EFF_START_DTTM	Effective Start Date/Time	UPDATE_DTTM
EFF_END_DTTM	Effective End Date/Time	System Variable: HIGH_DATE
DATA_LOAD_DTTM	Data Load Date/Time	System Variable: CURRENT_DATE
DATA_SOURCE_IND	Data Source Indicator	Stage: DATA_SOURCE_IND
JOB_NBR	Job Number	Job Control: JOB_NBR

Task Type Dimension <CD_TASK_TYPE>

The Task Type dimension stores details of the type of tasks assigned to the crew.

Properties

Property	Value
Table Type	Dimension
SCD Type	1

Fields

Column	OBIEE Field	Load
TASK_TYPE_KEY	Task Type Dimension Surrogate Key	Sequence: OUBI_TASK_TYPE_SEQ
TASK_TYPE_CD	Task Type Code	Stage: TASK_TYPE_CD
TASK_TYPE_DESCR	Task Type Description	Stage: TASK_TYPE_DESCR
TASK_CLASS_CD	Task Class Code	Stage: TASK_CLASS_CD
TASK_CLASS_DESCR	Task Class Description	Stage: TASK_CLASS_DESCR
PRIORITY_PROF_CD	Priority Profile Code	Stage: PRIORITY_PROF_CD
PRIORITY_PROF_DESCR	Priority Profile Description	Stage: PRIORITY_PROF_DESCR

SVC_CATEGORY_CD	Service Category Code	Stage: SVC_CATEGORY_CD
SVC_CATEGORY_DESCR	Service Category Description	Stage: SVC_CATEGORY_DESCR
RESP_TM_SLA	Response Time SLA	Stage: RESP_TM_SLA
UDF1_CD	User Defined Field Code	Stage: UDF1_CD
UDF1_DESCR	User Defined Field Description	Stage: UDF1_DESCR
UDF2_CD	User Defined Field Code	Stage: UDF2_CD
UDF2_DESCR	User Defined Field Description	Stage: UDF2_DESC
UDF3_CD	User Defined Field Code	Stage: UDF3_CD
UDF3_DESCR	User Defined Field Description	Stage: UDF3_DESC
UDF4_CD	User Defined Field Code	Stage: UDF4_CD
UDF4_DESCR	User Defined Field Description	Stage: UDF4_DESC
UDF5_CD	User Defined Field Code	Stage: UDF5_CD
UDF5_DESCR	User Defined Field Description	Stage: UDF5_DESC
UDF6_CD	User Defined Field Code	Stage: UDF6_CD
UDF6_DESCR	User Defined Field Description	Stage: UDF6_DESC
UDF7_CD	User Defined Field Code	Stage: UDF7_CD
UDF7_DESCR	User Defined Field Description	Stage: UDF7_DESC
UDF8_CD	User Defined Field Code	Stage: UDF8_CD
UDF8_DESCR	User Defined Field Description	Stage: UDF8_DESC
UDF9_CD	User Defined Field Code	Stage: UDF9_CD
UDF9_DESCR	User Defined Field Description	Stage: UDF9_DESC
UDF10_CD	User Defined Field Code	Stage: UDF10_CD
UDF10_DESCR	User Defined Field Description	Stage: UDF10_DESC
EFF_START_DTTM	Effective Start Date/Time	UPDATE_DTTM
EFF_END_DTTM	Effective End Date/Time	System Variable: HIGH_DATE

DATA_LOAD_DTTM	Data Load Date/Time	System Variable: CURRENT_DATE
DATA_SOURCE_IND	Data Source Indicator	Stage: DATA_SOURCE_IND
JOB_NBR	Job Number	Job Control: JOB_NBR

Service Area Dimension <CD_SERVICE_AREA>

The Service Area dimension stores details of the location where the crew performs activities.

Properties

Property	Value
Table Type	Dimension
SCD Type	1

Fields

Column	OBIEE Field	Load
SERVICE_AREA_KEY	Service area key	Sequence: SERVICE_AREA_KEY
DATA_LOAD_DTTM	Data Load Date/Time	System Variable: CURRENT_DATE
DATA_SOURCE_IND	Data Source Indicator	Stage: DATA_SOURCE_IND
JOB_NBR	Job Number	Job Control: JOB_NBR
UDF1_CD	User Defined Field Code	Stage: UDF1_CD
UDF1_DESCR	User Defined Field Description	Stage: UDF1_DESCR
UDF2_CD	User Defined Field Code	Stage: UDF2_CD
UDF2_DESCR	User Defined Field Description	Stage: UDF2_DESC
UDF3_CD	User Defined Field Code	Stage: UDF3_CD
UDF3_DESCR	User Defined Field Description	Stage: UDF3_DESC
UDF4_CD	User Defined Field Code	Stage: UDF4_CD
UDF4_DESCR	User Defined Field Description	Stage: UDF4_DESC
UDF5_CD	User Defined Field Code	Stage: UDF5_CD

UDF5_DESCR	User Defined Field Description	Stage: UDF5_DESC
UDF6_CD	User Defined Field Code	Stage: UDF6_CD
UDF6_DESCR	User Defined Field Description	Stage: UDF6_DESC
UDF7_CD	User Defined Field Code	Stage: UDF7_CD
UDF7_DESCR	User Defined Field Description	Stage: UDF7_DESC
UDF8_CD	User Defined Field Code	Stage: UDF8_CD
UDF8_DESCR	User Defined Field Description	Stage: UDF8_DESC
UDF9_CD	User Defined Field Code	Stage: UDF9_CD
UDF9_DESCR	User Defined Field Description	Stage: UDF9_DESC
UDF10_CD	User Defined Field Code	Stage: UDF10_CD
UDF10_DESCR	User Defined Field Description	Stage: UDF10_DESC
SERVICE_AREA_CD	Service Area Code	Stage: SERVICE_AREA_CD
SERVICE_AREA_DESCR	Service Area Description	Stage: SERVICE_AREA_DESCR
HIER_UNIT1_CD	Hierarchy Unit1 Code	Stage: HIER_UNIT1_CD
HIER_UNIT1_DESCR	Hierarchy Unit1 Description	Stage: HIER_UNIT1_DESCR
HIER_UNIT2_CD	Hierarchy Unit2 Code	Stage: HIER_UNIT2_CD
HIER_UNIT2_DESCR	Hierarchy Unit2 Description	Stage: HIER_UNIT2_DESCR
HIER_UNIT3_CD	Hierarchy Unit3 Code	Stage: HIER_UNIT3_CD
HIER_UNIT3_DESCR	Hierarchy Unit3 Description	Stage: HIER_UNIT3_DESCR
UPDATE_DTTM	Update Date/Time	Stage: UPDATED_DATE_TIME

Appointment Time Dimension <CD_APPT_TM>

The Appointment Time dimension stores the configurable time ranges in minutes that indicate whether the crew missed an appointment, and if so, by how much time.

Properties

Property	Value
Table Type	Dimension

Property	Value
SCD Type	1

Fields

Column	OBIEE Field	Load
APPT_TM_KEY	Appointment Time Dimension Surrogate Key	Auto generated key populated using OUBI_APPT_TM_SEQ
APPT_TM_CD	Appointment Time Code	
APPT_TM_DESCR	Appointment Time Description	
APPT_STATUS_CD	Appointment State Code	
APPT_STATUS_DESCR	Appointment State Description	
UDF1_CD	User Defined Field Code	Stage: UDF1_CD
UDF1_DESCR	User Defined Field Description	Stage: UDF1_DESC
UDF2_CD	User Defined Field Code	Stage: UDF2_CD
UDF2_DESCR	User Defined Field Description	Stage: UDF2_DESC
UDF3_CD	User Defined Field Code	Stage: UDF3_CD
UDF3_DESCR	User Defined Field Description	Stage: UDF3_DESC
UDF4_CD	User Defined Field Code	Stage: UDF4_CD
UDF4_DESCR	User Defined Field Description	Stage: UDF4_DESC
UDF5_CD	User Defined Field Code	Stage: UDF5_CD
UDF5_DESCR	User Defined Field Description	Stage: UDF5_DESC
UDF6_CD	User Defined Field Code	Stage: UDF6_CD
UDF6_DESCR	User Defined Field Description	Stage: UDF6_DESC
UDF7_CD	User Defined Field Code	Stage: UDF7_CD
UDF7_DESCR	User Defined Field Description	Stage: UDF7_DESC
UDF8_CD	User Defined Field Code	Stage: UDF8_CD

UDF8_DESCR	User Defined Field Description	Stage: UDF8_DESC
UDF9_CD	User Defined Field Code	Stage: UDF9_CD
UDF9_DESCR	User Defined Field Description	Stage: UDF9_DESC
UDF10_CD	User Defined Field Code	Stage: UDF10_CD
UDF10_DESCR	User Defined Field Description	Stage: UDF10_DESC
UPDATE_DTTM	Update Date/Time	Stage: UPDATED_DATE_TIME
DATA_LOAD_DTTM	Data Load Date/Time	System Variable: CURRENT_DATE
DATA_SOURCE_IND	Data Source Indicator	Stage: DATA_SOURCE_IND
JOB_NBR	Job Number	Job Control: JOB_NBR

Appointment Time of Day Dimension <CD_APPT_TM_OF_DAY>

The Appointment Time of Day dimension stores the configurable time ranges classifying an appointment time of day.

Properties

Property	Value
Table Type	Dimension
SCD Type	1

Fields

Column	OBIEE Field	Load
APPT_TM_OF_DAY_KEY	Appointment Time of Day Dimension Surrogate Key	Auto generated key populated using OUBI_APPT_TM_OF_DAY_SEQ
APPT_TM_OF_DAY_CD	Appointment Time Of Day Code	Natural Key
APPT_TM_OF_DAY_DESCR	Appointment Time of Day Description	Stage: APPT_TM_OF_DAY_DESC
UDF1_CD	User Defined Field Code	Stage: UDF1_CD
UDF1_DESCR	User Defined Field Description	Stage: UDF1_DESC

UDF2_CD	User Defined Field Code	Stage: UDF2_CD
UDF2_DESCR	User Defined Field Description	Stage: UDF2_DESC
UDF3_CD	User Defined Field Code	Stage: UDF3_CD
UDF3_DESCR	User Defined Field Description	Stage: UDF3_DESC
UDF4_CD	User Defined Field Code	Stage: UDF4_CD
UDF4_DESCR	User Defined Field Description	Stage: UDF4_DESC
UDF5_CD	User Defined Field Code	Stage: UDF5_CD
UDF5_DESCR	User Defined Field Description	Stage: UDF5_DESC
UDF6_CD	User Defined Field Code	Stage: UDF6_CD
UDF6_DESCR	User Defined Field Description	Stage: UDF6_DESC
UDF7_CD	User Defined Field Code	Stage: UDF7_CD
UDF7_DESCR	User Defined Field Description	Stage: UDF7_DESC
UDF8_CD	User Defined Field Code	Stage: UDF8_CD
UDF8_DESCR	User Defined Field Description	Stage: UDF8_DESC
UDF9_CD	User Defined Field Code	Stage: UDF9_CD
UDF9_DESCR	User Defined Field Description	Stage: UDF9_DESC
UDF10_CD	User Defined Field Code	Stage: UDF10_CD
UDF10_DESCR	User Defined Field Description	Stage: UDF10_DESC
UPDATE_DTTM	Update Date/Time	Stage: UPDATED_DATE_TIME
DATA_LOAD_DTTM	Data Load Date/Time	System Variable: CURRENT_DATE
DATA_SOURCE_IND	Data Source Indicator	Stage: DATA_SOURCE_IND
JOB_NBR	Job Number	Job Control: JOB_NBR

Travel Duration Deviation Dimension <CD_TRAVEL_DUR_DEV>

The Travel Duration Deviation dimension stores the configurable percentage ranges that indicate deviation of actual travel duration relative to estimated travel duration.

Properties

Property	Value
Table Type	Dimension
SCD Type	1

Fields

Column	OBIEE Field	Load
TRAVEL_DUR_DEV_KEY	Travel Duration Deviation Dimension Surrogate Key	Auto generated key populated using OUBI_TRAVEL_DUR_DEV _SEQ
TRAVEL_DUR_DEV_CD	Travel Duration Deviation Code	Natural Key
TRAVEL_DUR_DEV_DESC R	Travel Duration Deviation Description	Stage: TRAVEL_DUR_DEV_DESC
UDF1_CD	User Defined Field Code	Stage: UDF1_CD
UDF1_DESCR	User Defined Field Descrip- tion	Stage: UDF1_DESC
UDF2_CD	User Defined Field Code	Stage: UDF2_CD
UDF2_DESCR	User Defined Field Descrip- tion	Stage: UDF2_DESC
UDF3_CD	User Defined Field Code	Stage: UDF3_CD
UDF3_DESCR	User Defined Field Descrip- tion	Stage: UDF3_DESC
UDF4_CD	User Defined Field Code	Stage: UDF4_CD
UDF4_DESCR	User Defined Field Descrip- tion	Stage: UDF4_DESC
UDF5_CD	User Defined Field Code	Stage: UDF5_CD
UDF5_DESCR	User Defined Field Descrip- tion	Stage: UDF5_DESC
UDF6_CD	User Defined Field Code	Stage: UDF6_CD
UDF6_DESCR	User Defined Field Descrip- tion	Stage: UDF6_DESC
UDF7_CD	User Defined Field Code	Stage: UDF7_CD
UDF7_DESCR	User Defined Field Descrip- tion	Stage: UDF7_DESC
UDF8_CD	User Defined Field Code	Stage: UDF8_CD

UDF8_DESCR	User Defined Field Description	Stage: UDF8_DESC
UDF9_CD	User Defined Field Code	Stage: UDF9_CD
UDF9_DESCR	User Defined Field Description	Stage: UDF9_DESC
UDF10_CD	User Defined Field Code	Stage: UDF10_CD
UDF10_DESCR	User Defined Field Description	Stage: UDF10_DESC
UPDATE_DTTM	Update Date/Time	Stage: UPDATED_DATE_TIME
DATA_LOAD_DTTM	Data Load Date/Time	System Variable: CURRENT_DATE
DATA_SOURCE_IND	Data Source Indicator	Stage: DATA_SOURCE_IND
JOB_NBR	Job Number	Job Control: JOB_NBR

Late Logon Time Dimension <CD_LATE_LOGON_TM>

The Late Logon Time dimension stores the configurable time ranges, in minutes, that indicate by how much time the crew is late to log-on.

Properties

Property	Value
Table Type	Dimension
SCD Type	1

Fields

Column	OBIEE Field	Load
LATE_LOGON_TM_KEY	Late Logon Time Dimension Surrogate Key	Auto generated key Populated using OUBI_LATE_LOGON_TM_SEQ
LATE_LOGON_TM_CD	Late Logon Time Code	Natural Key
LATE_LOGON_TM_DESCR	Late Logon Time Description	Stage: LATE_LOGON_TM_DESCR

CONSIDERED_ONTIME_CD	Considered On Time Code	Stage: CONSIDERED_ONTIME_CD
CONSIDERED_ONTIME_DESCR	Considered On Time Description	Stage: CONSIDERED_ONTIME_DESCR
UDF1_CD	User Defined Field Code	Stage: UDF1_CD
UDF1_DESCR	User Defined Field Description	Stage: UDF1_DESC
UDF2_CD	User Defined Field Code	Stage: UDF2_CD
UDF2_DESCR	User Defined Field Description	Stage: UDF2_DESC
UDF3_CD	User Defined Field Code	Stage: UDF3_CD
UDF3_DESCR	User Defined Field Description	Stage: UDF3_DESC
UDF4_CD	User Defined Field Code	Stage: UDF4_CD
UDF4_DESCR	User Defined Field Description	Stage: UDF4_DESC
UDF5_CD	User Defined Field Code	Stage: UDF5_CD
UDF5_DESCR	User Defined Field Description	Stage: UDF5_DESC
UDF6_CD	User Defined Field Code	Stage: UDF6_CD
UDF6_DESCR	User Defined Field Description	Stage: UDF6_DESC
UDF7_CD	User Defined Field Code	Stage: UDF7_CD
UDF7_DESCR	User Defined Field Description	Stage: UDF7_DESC
UDF8_CD	User Defined Field Code	Stage: UDF8_CD
UDF8_DESCR	User Defined Field Description	Stage: UDF8_DESC
UDF9_CD	User Defined Field Code	Stage: UDF9_CD
UDF9_DESCR	User Defined Field Description	Stage: UDF9_DESC
UDF10_CD	User Defined Field Code	Stage: UDF10_CD
UDF10_DESCR	User Defined Field Description	Stage: UDF10_DESC
UPDATE_DT*TM	Update Date/Time	Stage: UPDATED_DATE_TIME

DATA_LOAD_DTTM	Data Load Date/Time	System Variable: CURRENT_DATE
DATA_SOURCE_IND	Data Source Indicator	Stage: DATA_SOURCE_IND
JOB_NBR	Job Number	Job Control: JOB_NBR

Early Logoff Time Dimension <CD_EARLY_LOGOFF_TM>

The Early Logoff Time dimension stores the configurable time ranges, in minutes, indicating by how much time the crew is logging off earlier than planned.

Properties

Property	Value
Table Type	Dimension
SCD Type	1

Fields

Column	OBIEE Field	Load
EARLY_LOGOFF_TM_KEY	Early Logoff Time Dimension Surrogate Key	Sequence: OUBI_EARLY_LOGOFF_TM_SEQ
EARLY_LOGOFF_TM_CD	Early Logoff Time Code	Stage: EARLY_LOGOFF_TM_CD
EARLY_LOGOFF_TM_DESCR	Early Logoff Time Description	Stage: EARLY_LOGOFF_TM_DESCR
CONSIDERED_ONTIME_CD	Considered On Time Code	Stage: CONSIDERED_ONTIME_CD
CONSIDERED_ONTIME_DESCR	Considered On Time Description	Stage: CONSIDERED_ONTIME_DESCR
UDF1_CD	User Defined Field Code	Stage: UDF1_CD
UDF1_DESCR	User Defined Field Description	Stage: UDF1_DESC
UDF2_CD	User Defined Field Code	Stage: UDF2_CD
UDF2_DESCR	User Defined Field Description	Stage: UDF2_DESC
UDF3_CD	User Defined Field Code	Stage: UDF3_CD

UDF3_DESCR	User Defined Field Description	Stage: UDF3_DESC
UDF4_CD	User Defined Field Code	Stage: UDF4_CD
UDF4_DESCR	User Defined Field Description	Stage: UDF4_DESC
UDF5_CD	User Defined Field Code	Stage: UDF5_CD
UDF5_DESCR	User Defined Field Description	Stage: UDF5_DESC
UDF6_CD	User Defined Field Code	Stage: UDF6_CD
UDF6_DESCR	User Defined Field Description	Stage: UDF6_DESC
UDF7_CD	User Defined Field Code	Stage: UDF7_CD
UDF7_DESCR	User Defined Field Description	Stage: UDF7_DESC
UDF8_CD	User Defined Field Code	Stage: UDF8_CD
UDF8_DESCR	User Defined Field Description	Stage: UDF8_DESC
UDF9_CD	User Defined Field Code	Stage: UDF9_CD
UDF9_DESCR	User Defined Field Description	Stage: UDF9_DESC
UDF10_CD	User Defined Field Code	Stage: UDF10_CD
UDF10_DESCR	User Defined Field Description	Stage: UDF10_DESC
UPDATE_DTTM	Update Date/Time	Stage: UPDATE_DTTM
DATA_LOAD_DTTM	Data Load Date/Time	System Variable: CURRENT_DATE
DATA_SOURCE_IND	Data Source Indicator	Stage: DATA_SOURCE_IND
JOB_NBR	Job Number	Job Control: JOB_NBR

Work Duration Deviation Dimension <CD_WORK_DUR_DEV>

The Work Duration Deviation dimension stores the configurable percentage ranges that indicate the deviation of actual work duration relative to the estimated work duration.

Properties

Property	Value
Table Type	Dimension

Property	Value
SCD Type	1

Fields

Column	OBIEE Field	Load
WORK_DUR_DEV_KEY	Work Duration Deviation Dimension Surrogate Key	Sequence: OUBI_WORK_DUR_DEV_ SEQ
WORK_DUR_DEV_CD	Work Duration Deviation Code	Stage: WORK_DUR_DEV_CD
WORK_DUR_DEV_DESCR	Work Duration Deviation Description	Stage: WORK_DUR_DEV_DESCR
UDF1_CD	User Defined Field Code	Stage: UDF1_CD
UDF1_DESCR	User Defined Field Descrip- tion	Stage: UDF1_DESC
UDF2_CD	User Defined Field Code	Stage: UDF2_CD
UDF2_DESCR	User Defined Field Descrip- tion	Stage: UDF2_DESC
UDF3_CD	User Defined Field Code	Stage: UDF3_CD
UDF3_DESCR	User Defined Field Descrip- tion	Stage: UDF3_DESC
UDF4_CD	User Defined Field Code	Stage: UDF4_CD
UDF4_DESCR	User Defined Field Descrip- tion	Stage: UDF4_DESC
UDF5_CD	User Defined Field Code	Stage: UDF5_CD
UDF5_DESCR	User Defined Field Descrip- tion	Stage: UDF5_DESC
UDF6_CD	User Defined Field Code	Stage: UDF6_CD
UDF6_DESCR	User Defined Field Descrip- tion	Stage: UDF6_DESC
UDF7_CD	User Defined Field Code	Stage: UDF7_CD
UDF7_DESCR	User Defined Field Descrip- tion	Stage: UDF7_DESC
UDF8_CD	User Defined Field Code	Stage: UDF8_CD
UDF8_DESCR	User Defined Field Descrip- tion	Stage: UDF8_DESC
UDF9_CD	User Defined Field Code	Stage: UDF9_CD

UDF9_DESCR	User Defined Field Description	Stage: UDF9_DESC
UDF10_CD	User Defined Field Code	Stage: UDF10_CD
UDF10_DESCR	User Defined Field Description	Stage: UDF10_DESC
UPDATE_DTTM	Update Date/Time	Stage: UPDATED_DATE_TIME
DATA_LOAD_DTTM	Data Load Date/Time	System Variable: CURRENT_DATE
DATA_SOURCE_IND	Data Source Indicator	Stage: DATA_SOURCE_IND
JOB_NBR	Job Number	Job Control: JOB_NBR

Travel Distance Deviation Dimension <CD_TRAVEL_DIST_DEV>

The Travel Distance Deviation dimension stores the configurable percentage ranges that indicate the deviation of actual distance relative to the estimated distance traveled by crew.

Properties

Property	Value
Table Type	Dimension
SCD Type	1

Fields

Column	OBIEE Field	Load
TRAVEL_DIST_DEV_KEY	Travel Distance Deviation Dimension Surrogate Key	OUBI_TRAVEL_DIST_DEV_SEQ
TRAVEL_DIST_DEV_CD	Travel Distance Deviation Code	CTRAVEL_DIST_DEV_CD
TRAVEL_DIST_DEV_DESCR	Travel Distance Deviation Description	TRAVEL_DIST_DEV_DESCR
UDF1_CD	User Defined Field Code	Stage: UDF1_CD
UDF1_DESCR	User Defined Field Description	Stage: UDF1_DESC
UDF2_CD	User Defined Field Code	Stage: UDF2_CD
UDF2_DESCR	User Defined Field Description	Stage: UDF2_DESC

UDF3_CD	User Defined Field Code	Stage: UDF3_CD
UDF3_DESCR	User Defined Field Description	Stage: UDF3_DESC
UDF4_CD	User Defined Field Code	Stage: UDF4_CD
UDF4_DESCR	User Defined Field Description	Stage: UDF4_DESC
UDF5_CD	User Defined Field Code	Stage: UDF5_CD
UDF5_DESCR	User Defined Field Description	Stage: UDF5_DESC
UDF6_CD	User Defined Field Code	Stage: UDF6_CD
UDF6_DESCR	User Defined Field Description	Stage: UDF6_DESC
UDF7_CD	User Defined Field Code	Stage: UDF7_CD
UDF7_DESCR	User Defined Field Description	Stage: UDF7_DESC
UDF8_CD	User Defined Field Code	Stage: UDF8_CD
UDF8_DESCR	User Defined Field Description	Stage: UDF8_DESC
UDF9_CD	User Defined Field Code	Stage: UDF9_CD
UDF9_DESCR	User Defined Field Description	Stage: UDF9_DESC
UDF10_CD	User Defined Field Code	Stage: UDF10_CD
UDF10_DESCR	User Defined Field Description	Stage: UDF10_DESC
UPDATE_DTTM	Update Date/Time	Stage: UPDATE_DTTM
DATA_LOAD_DTTM	Data Load Date/Time	System Variable: CURRENT_DATE
DATA_SOURCE_IND	Data Source Indicator	Stage: DATA_SOURCE_IND
JOB_NBR	Job Number	Job Control: JOB_NBR

Response Time Deviation Dimension <CD_RESP_TM_DEV>

The Response Time Deviation dimension stores the configurable ranges, in minutes, of the response time deviation from SLA.

Properties

Property	Value
Table Type	Dimension
SCD Type	1

Fields

Column	OBIEE Field	Load
RESP_TM_DEV_KEY	Response Time Deviation Dimension Surrogate Key	Sequence: OUBI_RESP_TM_DEV_SE Q
RESP_TM_DEV_CD	Response Time Deviation Code	Stage: RESP_TM_DEV_CD
RESP_TM_DEV_DESCR	Response Time Deviation Description	Stage: RESP_TM_DEV_DESCR
SLA_STATUS_CD	SLA State Code	Stage: SLA_STATE_CD
SLA_STATUS_DESCR	SLA State Description	Stage: SLA_STATE_DESCR
UDF1_CD	User Defined Field Code	Stage: UDF1_CD
UDF1_DESCR	User Defined Field Descrip- tion	Stage: UDF1_DESC
UDF2_CD	User Defined Field Code	Stage: UDF2_CD
UDF2_DESCR	User Defined Field Descrip- tion	Stage: UDF2_DESC
UDF3_CD	User Defined Field Code	Stage: UDF3_CD
UDF3_DESCR	User Defined Field Descrip- tion	Stage: UDF3_DESC
UDF4_CD	User Defined Field Code	Stage: UDF4_CD
UDF4_DESCR	User Defined Field Descrip- tion	Stage: UDF4_DESC
UDF5_CD	User Defined Field Code	Stage: UDF5_CD
UDF5_DESCR	User Defined Field Descrip- tion	Stage: UDF5_DESC
UDF6_CD	User Defined Field Code	Stage: UDF6_CD
UDF6_DESCR	User Defined Field Descrip- tion	Stage: UDF6_DESC
UDF7_CD	User Defined Field Code	Stage: UDF7_CD

UDF7_DESCR	User Defined Field Description	Stage: UDF7_DESC
UDF8_CD	User Defined Field Code	Stage: UDF8_CD
UDF8_DESCR	User Defined Field Description	Stage: UDF8_DESC
UDF9_CD	User Defined Field Code	Stage: UDF9_CD
UDF9_DESCR	User Defined Field Description	Stage: UDF9_DESC
UDF10_CD	User Defined Field Code	Stage: UDF10_CD
UDF10_DESCR	User Defined Field Description	Stage: UDF10_DESC
UPDATE_DTTM	Update Date/Time	Stage: UPDATE_DTTM
DATA_LOAD_DTTM	Data Load Date/Time	System Variable: CURRENT_DATE
DATA_SOURCE_IND	Data Source Indicator	Stage: DATA_SOURCE_IND
JOB_NBR	Job Number	Job Control: JOB_NBR

Address Dimension <CD_ADDR>

The Address dimension stores the location details of logon and logoff of crew (from Crew Shift) and also the location where the activity was performed.

Properties

Property	Value
Table Type	Dimension
SCD Type	2

Fields

Column	OBIEE Field	Load
ADDR_KEY	Address Key	Sequence: SPL_ADDR_SEQ
ADDR_LINE1	Address Line1	Stage: ADDR_LINE1
ADDR_LINE2	Address Line2	Stage: ADDR_LINE2
ADDR_LINE3	Address Line3	Stage: ADDR_LINE3
ADDR_LINE4	Address Line4	Stage: ADDR_LINE4
CROSS_STREET	Cross Street	Stage: CROSS_STREET

SUBURB	Suburb	Stage: SUBURB
CITY	City	Stage: CITY
COUNTY	County	Stage: COUNTY
POSTAL	Postal	Stage: POSTAL
STATE_CD	State Code	Stage: STATE_CD
STATE_DESCR	State Description	Stage: STATE_DESCR
COUNTRY_CD	Country Code	Stage: COUNTRY_CD
COUNTRY_DESCR	Country Description	Stage: COUNTRY_DESCR
GEO_CODE	Geo Code	Stage: GEO_CODE
UDF1_CD	User Defined Field Code	Stage: UDF1_CD
UDF1_DESCR	User Defined Field Description	Stage: UDF1_DESC
UDF2_CD	User Defined Field Code	Stage: UDF2_CD
UDF2_DESCR	User Defined Field Description	Stage: UDF2_DESC
UDF3_CD	User Defined Field Code	Stage: UDF3_CD
UDF3_DESCR	User Defined Field Description	Stage: UDF3_DESC
UDF4_CD	User Defined Field Code	Stage: UDF4_CD
UDF4_DESCR	User Defined Field Description	Stage: UDF4_DESC
UDF5_CD	User Defined Field Code	Stage: UDF5_CD
UDF5_DESCR	User Defined Field Description	Stage: UDF5_DESC
UDF6_CD	User Defined Field Code	Stage: UDF6_CD
UDF6_DESCR	User Defined Field Description	Stage: UDF6_DESC
UDF7_CD	User Defined Field Code	Stage: UDF7_CD
UDF7_DESCR	User Defined Field Description	Stage: UDF7_DESC
UDF8_CD	User Defined Field Code	Stage: UDF8_CD
UDF8_DESCR	User Defined Field Description	Stage: UDF8_DESC
UDF9_CD	User Defined Field Code	Stage: UDF9_CD
UDF9_DESCR	User Defined Field Description	Stage: UDF9_DESC


UDF10_CD	User Defined Field Code	Stage: UDF10_CD
UDF10_DESCR	User Defined Field Description	Stage: UDF10_DESC
EFF_START_DTTM	Effective Start Date/Time	Stage: UPDATE_DTTM
EFF_END_DTTM	Effective End Date/Time	System Variable: HIGH_DATE
DATA_LOAD_DTTM	Data Load Date/Time	System Variable: CURRENT_DATE
DATA_SOURCE_IND	Data Source Indicator	Stage: DATA_SOURCE_IND
JOB_NBR	Job Number	Job Control: JOB_NBR
SRC_ADDR_ID	Address ID	Stage: SRC_ADDR_ID
ADDR_INFO	Address Description	Stage: ADDR_INFO

Fact Table Schema

Crew Tasks Fact <CF_CREW_TASK>

The Crew Task fact accumulates the shift and task log tables' state transition entries for all completed shifts.

Entity Relationship Diagram



Properties

Property	Value
Table Type	Fact
Fact Type	Accumulation
Materialized View	B1_CREW_TASKS_MON_MV1

Fields

Field	OBIEE Field	Load
CREW_TASK_KEY	Crew Task Surrogate Key	Sequence: Required OUBI_CREW_TASK_SEQ
PREV_STATE_DUR	Time in Previous State	Stage: TIME_IN_PREVIOUS_STATE

Field	OBIEE Field	Load
APPOINTMENT_IND	Appointment Indicator	Stage: APPOINTMENT_IND
EMERGENCY_IND	Emergency Indicator	Stage: EMERGENCY_IND
EST_TRAVEL_DUR	Estimated Travel Time	Stage: ESTIMATED_TRAVEL_TIME
FACT_CNT	Count	Numeric Constant: 1
SRC_SHIFT_ID	Shift ID	Stage: Required SHIFT_ID
SRC_TASK_ID	Crew Task ID	Stage: TASK_ID
SRC_SHIFT_LOG_SEQ	Shift Log Sequence	Stage: Required SHIFT_LOG_SEQUENCE
SRC_TASK_LOG_SEQ	Task Log Sequence	Stage: TASK_LOG_SEQUENCE
FROM_DTTM	From Date/Time	Stage: FROM_DTTM
TO_DTTM	To Date/Time	Stage: TO_DTTM
CREW_TM_USG_KEY	Crew Time Usage Dimension Surrogate Key	Join: Required CD_CREW_TM_USG.CREQ_TIME_USAGE_CD
FROM_SHIFT_BO_STATUS_KEY	Shift BO Status Dimension Surrogate Key	Join: Required CD_SHIFT_BO_STATUS.FROM_SHIFT_BO_CD
TO_SHIFT_BO_STATUS_KEY	Shift BO Status Dimension Surrogate Key	Join: Required CD_SHIFT_BO_STATUS.FROM_BO_STATUS_CD
CREW_SHIFT_KEY	Shift Dimension Surrogate Key	Join: Required CD_CREW_SHIFT.CREW_SHIFT_KEY
CREW_KEY	Crew Dimension Surrogate Key	Join: Required CD_CREW.CREW_CD
TRAVEL_DUR_DEV_KEY	Travel Duration Deviation Dimension Surrogate Key	Join: Required CD_TRAVEL_DUR_DEV.TRAVEL_DURATION_DEVIATION_CD
APPT_TM_KEY	Appointment Time Dimension Surrogate Key	Join: Required CD_APPT_TM.APPOINTMENT_TIME_CD
APPT_TM_OF_DAY_KEY	Appointment Time of Day Dimension Surrogate Key	Join: Required CD_APPT_TM_OF_DAY.APPOINTMENT_TIME_OF_DAY_CD
FROM_TASK_BO_STATUS_KEY	Task BO Status Dimension Surrogate Key	Join: Required CD_TASK_BO_STATUS.FROM_TASK_BO_CD
TO_TASK_BO_STATUS_KEY	Task BO Status Dimension Surrogate Key	Join: Required CD_TASK_BO_STATUS.TO_TASK_BO_CD

Field	OBIEE Field	Load
TASK_TYPE_KEY	Task Type Dimension Surrogate Key	Join: Required CD_TASK_TYPE.TASK_TYPE_CD
SERVICE_AREA_KEY	Service Area Dimension Surrogate Key	Join: Required CD_SERVICE_AREA.SERVICE_AREA_CD
ADDR_KEY	Address Dimension Surrogate Key	Join: Required CD_ADDR.ADDRESS_ID
FROM_DATE_KEY	Date Dimension Surrogate Key	Join: Required CD_DATE.FROM_DATE
TO_DATE_KEY	Date Dimension Surrogate Key	Join: Required CD_DATE.TO_DATE
FROM_TIME_KEY	Time Dimension Surrogate Key	Join: Required CD_TIME.FROM_TIME
TO_TIME_KEY	Time Dimension Surrogate Key	Join: Required CD_TIME.TO_TIME
MTR_DEVICE_KEY	Device Dimension Surrogate Key	Join: Optional CD_MTR_DEVICE.DEVICE_ID
SP_KEY	Service Point Dimension Surrogate Key	Join: Optional CD_SP.SERVICE_POINT_ID
US_KEY	Usage Subscription Dimension Surrogate Key	Join: Optional CD_US.USG_SUBSCRIPTION_ID
CONTACT_KEY	Contact Dimension Surrogate Key	Join: Optional CD_CONTACT.CONTACT_KEY
PER_KEY	CCB Person Dimension Foreign Key	Join: Optional CD_PER.PERSON_ID
ACCT_KEY	CCB Account Dimension Foreign Key	Join: Optional CD_ACCT.ACCOUNT_ID
SA_KEY	CCB SA Dimension Foreign Key	Join: Optional CD_SA.SA_ID
PREM_KEY	CCB Premise Dimension Foreign Key	Join: Optional CD_PREM.PREMISE_ID
CREW_TASK_UDD1_KEY	User Defined Degenerate Dimension 1	Join: Optional CD_CREW_TASK_UDD1.UDD1_CD
CREW_TASK_UDD2_KEY	User Defined Degenerate Dimension 2	Join: Optional CD_CREW_TASK_UDD2.UDD2_CD
UDM1	User Defined Measure 1	Stage: UDM1
UDM2	User Defined Measure 2	Stage: UDM2
UDM3	User Defined Measure 3	Stage: UDM3
UDM4	User Defined Measure 4	Stage: UDM4
UDM5	User Defined Measure 5	Stage: UDM5

Field	OBIEE Field	Load
UDM6	User Defined Measure 6	Stage: UDM6
UDM7	User Defined Measure 7	Stage: UDM7
UDM8	User Defined Measure 8	Stage: UDM8
UDM9	User Defined Measure 9	Stage: UDM9
UDM10	User Defined Measure 10	Stage: UDM10
UDDGEN1	User Defined Degenerate Dimension 1	Stage: UDDGEN1
UDDGEN2	User Defined Degenerate Dimension 2	Stage: UDDGEN2
UDDGEN3	User Defined Degenerate Dimension 3	Stage: UDDGEN3
UDDGEN4	User Defined Degenerate Dimension 4	Stage: UDDGEN4
UDDGEN5	User Defined Degenerate Dimension 5	Stage: UDDGEN5
UDDGENL1	User Defined Long Degenerate Dimension 1	Stage: UDDGENL1
UDDGENL2	User Defined Long Degenerate Dimension 2	Stage: UDDGENL2
UDDGENL3	User Defined Long Degenerate Dimension 3	Stage: UDDGENL3
UDDGENL4	User Defined Long Degenerate Dimension 4	Stage: UDDGENL4
UDDGENL5	User Defined Long Degenerate Dimension 5	Stage: UDDGENL5
UDDFK1_KEY	User Defined Dimension Foreign Key 1	Stage: UDDFK1_KEY
UDDFK2_KEY	User Defined Dimension Foreign Key 2	Stage: UDDFK2_KEY
UDDFK3_KEY	User Defined Dimension Foreign Key 2	Stage: UDDFK3_KEY
UDDFK4_KEY	User Defined Dimension Foreign Key 2	Stage: UDDFK4_KEY
UDDFK5_KEY	User Defined Dimension Foreign Key 2	Stage: UDDFK5_KEY
DATA_SOURCE_IND	Data Source Indicator	Stage: DATA_SOURCE_IND
JOB_NBR	Job Number	Job Control: JOB_NBR
	Total Time	Sum(PREV_STATE_DUR)

Field	OBIEE Field	Load
	% Of Total	(Non-Productive/Total Time)*100
	Productive Time	case when "Core"."CD_CREW_TM_USG"."PRODUCTIVITY_CD" = 'M1PR' then "Core"."CF_CREW_TASK"."PREV_STATE_DUR" else 0 end
	Non Productive Time	case when "Core"."CD_CREW_TM_USG"."PRODUCTIVITY_CD" = 'M1NP' then "Core"."CF_CREW_TASK"."PREV_STATE_DUR" else 0 end
	Utilization%	SUM("CF_CREW_TASK"."PRODUCTIVE_TIME")/ (SUM("CF_CREW_TASK"."PRODUCTIVE_TIME") + SUM("CF_CREW_TASK"."NON_PRODUCTIVE_TIME")) * 100
	Total Time Duration	CF_CREW_TASK.Sum("PREV_STATE_DUR") - Set to Total level in the Crew_TM_USG Hierarchy
	Productive Time (Mins)	Case when "Core"."CD_CREW_TM_USG"."PRODUCTIVITY_CD" = 'M1PR' then "Core"."CF_CREW_TASK"."PREV_STATE_DUR_TOTAL" else 0 end
	% of Total Time	("Core"."CF_CREW_TASK"."PREV_STATE_DUR_TOTAL" * 100)/ ("Core"."CF_CREW_TASK"."TOT_TIME_DUR")
	% Total Productive Time	("Core"."CF_CREW_TASK"."PREV_STATE_DUR_TOTAL" * 100) / "Core"."CF_CREW_TASK"."PRODUCTIVE_TIME"
	Average Time Per Crew (Mins)	"SUM(CF_CREW_TASK"."PREV_STATE_DUR")/Total Shift Count
	Total Duration	CF_CREW_TASK.Sum("PREV_STATE_DUR")
	% Total Non Productive Time	("Core"."CF_CREW_TASK"."PREV_STATE_DUR_TOTAL" * 100) / "Core"."CF_CREW_TASK"."NONPRODUCTIVE_TIME"
	Number of Shifts	count(distinct CF_CREW_TASK.SRC_SHIFT_ID)
	Average Time	Average is calculated for based on total hours for each time bucket for the selected time period divided by the total number of shifts.


Field	OBIEE Field	Load
	Rank N	Rank("Core"."CF_CREW_TASK"."PROD_%OF_TOTAL" * (-1))
	Productive Time as % of Total	("Core"."CF_CREW_TASK"."PRODUCTIVE_TIME" * 100)/ ("Core"."CF_CREW_TASK"."TOT_TIME_DUR")
	IdleTime	CASE WHEN "Core"."CD_CREW_TM_USG"."CREW_TM_USG_CD" = 'IDLE' THEN "Core"."CF_CREW_TASK"."PREV_STATE_DUR_TOTAL" ELSE 0 END
	Rank (Idle Time)	Rank("Core"."CF_CREW_TASK"."CREW_IDLE_TIME")
	Idle Time as % Total	((("Core"."CF_CREW_TASK"."CREW_IDLE_TIME") * 100)/ ("Core"."CF_CREW_TASK"."TOT_TIME_DUR")
	Average	(sum("CF_CREW_TASK"."CREW_IDLE_TIME")*100)/ sum("CF_CREW_TASK"."TOT_TIME_DUR")
	Total Shift Time	Filter("Core"."CF_CREW_TASK"."PREV_STATE_DUR_TOTAL" Using "Core"."CD_CREW_TM_USG"."PRODUCTIVITY_CD" = 'M1NP' OR "Core"."CD_CREW_TM_USG"."PRODUCTIVITY_CD" = 'M1PR')
	Number of activities	Calculated column : Number Of Activities = SUM(CF_CREW_TASK.FACT_CNT)
	Number of incomplete activities	Calculated column : Number of Incomplete Activities = Sum(case when CD_TASK_BO_STATUS.INCOMPLETE_IND =1 then CF_CREW_TASK.FACT_CNT) Join with status_date_key
	%Incomplete	Runtime Column: Number of Incomplete Activities / Number Of Activities * 100
	Number of Activities in deviation Category	Count(distinct task id) where record exists in dev category dimension
	Average Productive Time	Productive time/Number of shifts

Field	OBIEE Field	Load
	Actual Travel Time	(FILTER("Core"."CF_CREW_TASK"."PRE V_STATE_DUR_TOTAL" using "Core"."CD_CREW_TM_USG"."CREW_T M_USG_CD" = 'M1TRAVEL'))/60
	Estimated Travel Time	("Core"."CF_CREW_TASK"."EST_TRAVE L_DUR" / 60)

Completed Shift Fact <CF_CMP_SHIFT>

The Completed Shift fact is an accumulation fact that captures details of all the completed shifts.

Entity Relationship Diagram



Properties

Property	Value
Table Type	Fact
Fact Type	Accumulation
Materialized View	B1_CMP_SHIFT_MON_MV1

Fields

Field	OBIEE Field	Load
CMP_SHIFT_KEY	Completed Shift Surrogate Key	Sequence: Required OUBI_CMP_SHIFT_SEQ
PLANNED_DUR	Planned Duration	Stage: PLANNED_DURATION
ACTUAL_DUR	Actual Duration	Stage: ACTUAL_DURATION
OVERTIME_DUR	Overtime Duration	Stage: OVERTIME_DURATION
EST_DISTANCE	Estimated Distance	Stage: ESTIMATED_DISTANCE

Field	OBIEE Field	Load
EST_TOT_MILEAGE	Estimated Total Mileage	Stage: ESTIMATED_TOTAL_MIL
ACT_TOT_MILEAGE	Actual Total Mileage	Stage: ACTUAL_TOTAL_MIL
VEHICLE_CNT	# Vehicles	Stage: VEHICLES
FACT_CNT	Count	Stage: 1
SRC_SHIFT_ID	Crew Shift ID	Stage: Required SHIFT_ID
SHIFT_PLANNED_START_DTTM	From Date/Time	Stage: SHIFT_PLAN_ST_DATE
CREW_SHIFT_KEY	Shift Dimension Surrogate Key	
CREW_KEY	Crew Dimension Surrogate Key	Join: Required CD_CREW.CREW_CODE
LATE_LOGON_TM_KEY	Late Logon Time Dimension Surrogate Key	Join: Required CD_LATE_LOGON_TM.LATE_LOG_TIME_DC
EARLY_LOGOFF_TM_KEY	Early Logoff Time Dimension Surrogate Key	Join: Required CD_EARLY_LOGOFF_TM.EARLY_LOG_TIME_CD
TRAVEL_DIST_DEV_KEY	Travel Distance Deviation Dimension Surrogate Key	Join: Required CD_TRAVEL_DIST_DEV.TRAVEL_DIST_DEV_CD
LOGON_ADDR_KEY	Address Dimension Surrogate Key	Join: Required CD_ADDR.LOG_ADDRESS_ID
LOGOFF_ADDR_KEY	Address Dimension Surrogate Key	Join: Required CD_ADDR.LOGOFF_ADDRESS_ID
SHIFT_PLANNED_START_DATE_KEY	Date Dimension Surrogate Key	Join: Required CD_DATE.SHIFT_PLAN_ST_DATE
SHIFT_PLANNED_START_TIME_KEY	Time Dimension Surrogate Key	Join: Required CD_DATE.SHIFT_PLAN_ST_TIME
CMP_SHIFT_UDD1_KEY	User Defined Degenerate Dimension 1	Join: CD_CMP_SHIFT_UDD1.UDD1_DC
CMP_SHIFT_UDD2_KEY	User Defined Degenerate Dimension 2	Join: CD_CMP_SHIFT_UDD2.UDD2_DC
UDM1	User Defined Measure 1	Stage: UDM1
UDM2	User Defined Measure 2	Stage: UDM2
UDM3	User Defined Measure 3	Stage: UDM3
UDM4	User Defined Measure 4	Stage: UDM4

Field	OBIEE Field	Load
UDM5	User Defined Measure 5	Stage: UDM5
UDM6	User Defined Measure 6	Stage: UDM6
UDM7	User Defined Measure 7	Stage: UDM7
UDM8	User Defined Measure 8	Stage: UDM8
UDM9	User Defined Measure 9	Stage: UDM9
UDM10	User Defined Measure 10	Stage: UDM10
UDDGEN1	User Defined Degenerate Dimension 1	Stage: UDDD1
UDDGEN2	User Defined Degenerate Dimension 2	Stage: UDDD2
UDDGEN3	User Defined Degenerate Dimension 3	Stage: UDDD3
UDDGEN4	User Defined Degenerate Dimension 4	Stage: UDDD4
UDDGEN5	User Defined Degenerate Dimension 5	Stage: UDDD5
UDDGENL1	User Defined Long Degenerate Dimension 1	Stage: UDLDD1
UDDGENL2	User Defined Long Degenerate Dimension 2	Stage: UDLDD2
UDDGENL3	User Defined Long Degenerate Dimension 3	Stage: UDLDD3
UDDGENL4	User Defined Long Degenerate Dimension 4	Stage: UDLDD4
UDDGENL5	User Defined Long Degenerate Dimension 5	Stage: UDLDD5
UDDFK1_KEY	User Defined Dimension Foreign Key 1	Stage: UDDFK_ID1
UDDFK2_KEY	User Defined Dimension Foreign Key 2	Stage: UDDFK_ID2
UDDFK3_KEY	User Defined Dimension Foreign Key 3	Stage: UDDFK_ID3
UDDFK4_KEY	User Defined Dimension Foreign Key 4	Stage: UDDFK_ID4
UDDFK5_KEY	User Defined Dimension Foreign Key 5	Stage: UDDFK_ID5
DATA_SOURCE_IND	Data Source Indicator	Stage: Required DATA_SOURCE_IND
JOB_NBR	Job Number	Job Control: JOB_NBR


Field	OBIEE Field	Load
	On Time shift Count	Sum(case when CD_LATE_LOGON_TM. CONSIDERED_ONTIME_CD = 'M1YS' and CD_EARLY_LOGOFF_TM. CONSIDERED_ONTIME_CD = 'M1YS' then FACT_CNT else 0 end)
	Total Shifts	SUM(FACT_CNT)
	% Of Total	On Time Shift Count/Total * 100
	% Of Actual	(Overtime Duration/Actual Duration)*100
	Total Shift Count	Sum of Fact Count with aggregation level set to Crew Time Usage Total
	Shifts with Late Starts	filter ("Core"."CF_CMP_SHIFT"."TOT_SHIFT" using "Core"."CD_LATE_LOGON_TM"."CON SIDERED_ONTIME_CD" = 'M1NO')
	% Of Total Shifts	((("Core"."CF_CMP_SHIFT"."LATE_SHIFT S") * 100) / ("Core"."CF_CMP_SHIFT"."TOT_SHIFT_ CNT")
	Shifts with Early Finish	filter("Core"."CF_CMP_SHIFT"."TOT_SHIFT" using "Core"."CD_EARLY_LOGOFF_TM"."CO NSIDERED_ONTIME_CD" = 'M1NO')
	% of Total	((("Core"."CF_CMP_SHIFT"."EARLY_LOG _SHIFT S") * 100) / ("Core"."CF_CMP_SHIFT"."TOT_SHIFT_ CNT")
	Overtime as % of Regular	Overtime/Regular Time * 100
	Overtime as % of Planned	Overtime/Planned Duration * 100
	Number of Shifts by Deviation Category	TOT_SHIFT_CNT set at late logon time deviation level
	Late Shifts	case when "Core"."CD_LATE_LOGON_TM"."CONS IDERED_ONTIME_CD" = 'M1NO' then "Core"."CF_CMP_SHIFT"."FACT_CNT_O NTIME" else 0 end
	Avg Actual Mileage	"Core"."CF_CMP_SHIFT"."ACT_TOT_MI LEAGE" / "Core"."CF_CMP_SHIFT"."VEHICLE_CN T"

Field	OBIEE Field	Load
	Avg Estimated Mileage	"Core"."CF_CMP_SHIFT"."EST_TOT_MILEAGE" / "Core"."CF_CMP_SHIFT"."VEHICLE_COUNT"
	% Deviation	("Core"."CF_CMP_SHIFT"."ACT_TOT_MILEAGE" - "Core"."CF_CMP_SHIFT"."EST_TOT_MILEAGE") * 100 / "Core"."CF_CMP_SHIFT"."EST_TOT_MILEAGE"
	Percent of On-Time shifts	("Core"."CF_CMP_SHIFT"."ON_TIME_SHIFTS" * 100) / ("Core"."CF_CMP_SHIFT"."TOT_SHIFT_COUNT")
	Total Shifts for Early Logon	Shift Count set at Early Logon Deviation bucket level
	Actual Duration(Hrs)	Actual Duration/60
	Overtime Duration (Hrs)	Overtime Duration / 60
	Planned Duration (Hrs)	Planned Duration /60

Field Activity Fact <CF_FLD_ACTIVITY>

The Field Activity fact is an accumulation fact that stores the activity details and their response times.

Entity Relationship Diagram



Properties

Property	Value
Table Type	Fact
Fact Type	Accumulation
Materialized View	B1_FLD_ACTIVITY_MON_MV1 B1_FLD_ACTIVITY_MON_MV2 B1_FLD_ACTIVITY_MON_MV3

Fields

Field	OBIEE Field	Load
FLD_ACTIVITY_KEY	Activity Surrogate Key	Sequence: Required OUBI_FLD_ACTIVITY_SEQ
TASK_INFO	Task Info String	Stage: TASK_ID
EMERGENCY_IND	Emergency Indicator	Stage: EMERGENCY_INDICATOR

Field	OBIEE Field	Load
APPOINTMENT_IND	Appointment Indicator	Stage: APPOINT_INDC
SAME_DAY_APPT_IND	Same Day Appointment Indicator	Stage: SAMEDAY_APPONT_INDC
WORK_DUR	Typical Work Duration	Stage: TYPICAL_WRK_DUR
EST_WORK_DUR	Estimated Work Duration	Stage: EST_WRK_DUR
ACT_WORK_DUR	Actual Work Duration	Stage: ACTUAL_WRK_DUR
ACT_TRAVEL_DUR	Actual Travel Duration	
WORK_ATTEMPT_CNT	Number of Work Attempts	Stage: WORK_ATTEMPTS
TRAVEL_ATTEMPT_CNT	Number of Travel Attempts	Stage: TRAVEL_ATTEMPTS
DISPATCH_RESP_DUR	Response Time Until Dispatched	Stage: RESPONSE_TIME_UNTIL_DISP
ENROUTE_RESP_DUR	Response Time Until Enroute	Stage: RESPONSE_TIME_UNTIL_ENRO
ARRIVAL_RESP_DUR	Response Time Until Arrived	Stage: RESPONSE_TIME_UNTIL_ARRIVED
COMPLETED_RESP_DUR	Response Time Until Completed	Stage: RESPONSE_TIME_UNTIL_COMP
TOT_RESP_DUR	Overall Response Time	Stage: OVERALL_RESPONSE_TIME
FACT_CNT	Count	Numeric Constant: 1
CRE_DT_TM	Creation Date/Time	Stage: CREATION_DATE
STATUS_DT_TM	Status Date/Time	Stage: STATUS_DATE
SCHED_START_DT_TM	Schedule Start Date/Time	Stage: SCHEDULE_START_DATETIME
SCHED_END_DT_TM	Schedule End Date/Time	Stage: SCHEDULE_END_DATETIME
SRC_TASK_ID	Crew Task ID	Stage: TASK_ID
TASK_BO_STATUS_KEY	Task BO Status Dimension Surrogate Key	Join: Required CD_TASK_BO_STATUS.TASK_BO_CD
TASK_TYPE_KEY	Task Type Dimension Surrogate Key	Join: Required CD_TASK_TYPE.TASK_INFO
SERVICE_AREA_KEY	Service Area Dimension Surrogate Key	Join: Required CD_SERVICE_AREA.SERVICE_AREA_CD
ADDR_KEY	Task Address Dimension Surrogate Key	Join: Required CD_ADDR.ADDRESS_ID

Field	OBIEE Field	Load
CREW_KEY	Crew Dimension Surrogate Key	Join: Required CD_CREW.CREW_CD
APPT_TM_KEY	Appointment Time Dimension Surrogate Key	Join: Required CD_APPT_TM.APPOINTMENT_TIME_CD
APPT_TM_OF_DAY_KEY	Appointment Time Of Day Dimension Surrogate Key	Join: Required CD_APPT_TM_OF_DAY.APPOINTMENT_TIME_DAY_CD
WORK_DUR_DEV_KEY	Work Duration Deviation Dimension Surrogate Key	Join: Required CD_WORK_DUR_DEV.WRL_DUR_DEV_CD
RESP_TM_DEV_KEY	Response Time Deviation Dimension Surrogate Key	Join: Required CD_RESP_TM_DEV.RESPONSE_TIME_DEV_CD
CRE_DATE_KEY	Date Dimension Surrogate Key	Join: Required CD_DATE.CREATION_DATE
STATUS_DATE_KEY	Date Dimension Surrogate Key	Join: Required CD_DATE.STATUS_DATE
SCHED_START_DATE_KEY	Date Dimension Surrogate Key	Join: Required CD_DATE.SCHEDULE_START_DATE
SCHED_END_DATE_KEY	Date Dimension Surrogate Key	Join: Required CD_DATE.SCHEDULE_END_DATE
CRE_TIME_KEY	Time Dimension Surrogate Key	Join: Required CD_TIME.CREATION_TIME
STATUS_TIME_KEY	Time Dimension Surrogate Key	Join: Required CD_TIME.STATUS_TIME
SCHED_START_TIME_KEY	Time Dimension Surrogate Key	Join: Required CD_TIME.SCHEDULE_START_TIME
SCHED_END_TIME_KEY	Time Dimension Surrogate Key	Join: Required CD_TIME.SCHEDULE_END_TIME
MTR_DEVICE_KEY	Device Dimension Surrogate Key	Join: CD_MTR_DEVICE.DEVICE_ID
SP_KEY	Service Point Dimension Surrogate Key	Join: CD_SP.SERVICE_POINT_ID
US_KEY	Usage Subscription Dimension Surrogate Key	Join: CD_US.USAGE_SUBSCRIPT_ID
CONTACT_KEY	Contact Dimension Surrogate Key	Join: CD_CONTACT.CONTACT_ID
PER_KEY	CCB Person Dimension Foreign Key	Join: CD_PER.PERSON_ID
ACCT_KEY	CCB Account Dimension Foreign Key	Join: CD_ACCT.ACCOUNT_ID
SA_KEY	CCB SA Dimension Foreign Key	Join: CD_SA.SA_ID

Field	OBIEE Field	Load
PREM_KEY	CCB Premise Dimension Foreign Key	Join: CD_PREM.PREMISE_ID
FLD_ACTIVITY_UDD1_KEY	User Defined Degenerate Dimension 1	Join: CD_FLD_ACTIVITY_UDD1.UDD1_CD
FLD_ACTIVITY_UDD2_KEY	User Defined Degenerate Dimension 2	Join: CD_FLD_ACTIVITY_UDD2.UDD2_CD
UDM1	User Defined Measure 1	Stage: UDM1
UDM2	User Defined Measure 2	Stage: UDM2
UDM3	User Defined Measure 3	Stage: UDM3
UDM4	User Defined Measure 4	Stage: UDM4
UDM5	User Defined Measure 5	Stage: UDM5
UDM6	User Defined Measure 6	Stage: UDM6
UDM7	User Defined Measure 7	Stage: UDM7
UDM8	User Defined Measure 8	Stage: UDM8
UDM9	User Defined Measure 9	Stage: UDM9
UDM10	User Defined Measure 10	Stage: UDM10
UDDGEN1	User Defined Degenerate Dimension 1	Stage: UDDD1
UDDGEN2	User Defined Degenerate Dimension 2	Stage: UDDD2
UDDGEN3	User Defined Degenerate Dimension 3	Stage: UDDD3
UDDGEN4	User Defined Degenerate Dimension 4	Stage: UDDD4
UDDGEN5	User Defined Degenerate Dimension 5	Stage: UDDD5
UDDGENL1	User Defined Long Degenerate Dimension 1	Stage: UDLDD1
UDDGENL2	User Defined Long Degenerate Dimension 2	Stage: UDLDD2
UDDGENL3	User Defined Long Degenerate Dimension 3	Stage: UDLDD3
UDDGENL4	User Defined Long Degenerate Dimension 4	Stage: UDLDD4
UDDGENL5	User Defined Long Degenerate Dimension 5	Stage: UDLDD5
UDDFK1_KEY	User Defined Dimension Foreign Key 1	Stage: UDDFK_ID1

Field	OBIEE Field	Load
UDDFK2_KEY	User Defined Dimension Foreign Key 2	Stage: UDDFK_ID2
UDDFK3_KEY	User Defined Dimension Foreign Key 3	Stage: UDDFK_ID3
UDDFK4_KEY	User Defined Dimension Foreign Key 4	Stage: UDDFK_ID4
UDDFK5_KEY	User Defined Dimension Foreign Key 5	Stage: UDDFK_ID5
DATA_SOURCE_IND	Data Source Indicator	Stage: DATA_SOURCE_IND
JOB_NBR	Job Number	Job Control: JOB_NBR
	Scheduled Activity Count	Sum(Fact Cnt) where status = Scheduled Join with status_date_key from cd_date
	Completed Activity Count	Sum(Fact Cnt) where status = Completed Join with scheduled_date_key from Cd_date
	Emergency Indicator	Indicator = 1
	Closed Count	Sum(case when CD_TASK_BO_STATUS.INCOMPLETE_IND =0 and CD_TASK_BO_STATUS.STATUS_CD='COMPLETED' and CF_FLD_ACTIVITY.APPOINTMENT_IND=1 then CF_FLD_ACTIVITY.FACT_CNT else 0 end) Join with status_date_key from cd_date
	Total Count	sum(CF_FLD_ACTIVITY.FACT_CNT) where CF_FLD_ACTIVITY.APPOINTMENT_IND=1
	Appointment Close Rate	Closed Count/Total Count * 100
	Missed SLA Count	Sum(Fact Cnt) where Response Time Deviation Dimension. SLA Status = Missed
	% Missed SLA	Missed SLA Count/Count * 100
	Scheduled Activity Count	Sum(case when SCHED_START_DTTM is not null then CF_FLD_ACTIVITY.FACT_CNT else 0 end) Join with Scheduled_start_date_key from Cd_date
	%completed	(CF_FLD_ACTIVITY.CMP_CNT * 100) / CF_FLD_ACTIVITY .SCHED_CNT

Field	OBIEE Field	Load
	Number of Activities	Calculated column : Number Of Completed Activities= Sum (Case when CD_TASK_BO_STATUS.INCOMPLETE_IND =0 then CF_FLD_ACTIVITY.FACT_CNT Else 0 end) Join with Status_date_key from CD_Date
	# of Activities	Calculated field : # Of Activities = Sum(CF_FLD_ACTIVITY.WORK_ATTEMPT_CNT > 1)
	Number of Attempts	Sum(CF_FLD_ACTIVITY.WORK_ATTEMPT_CNT)
	% Total	Calculated column: % Of Total Activities Cancelled = Sum (Case when CD_TASK_BO_STATUS.STATUS_CD = 'CANCELED' then CF_FLD_ACTIVITY.FACT_CNT else 0 end) Join with status_date_key from cd_date
	Number Of Emergencies	SUM(CF_FLD_ACTIVITY.FACT_CNT) where EMERGENCY_IND=1
	Average # of Emergencies for month	((SUM("CF_FLD_ACTIVITY"."EMERGENCY_IND"))*100/ (SUM("CF_FLD_ACTIVITY"."TOT_ACTIVITY_CNT"))/ (MAX("CD_DATE"."CAL_MONTH_NBR")- MIN("CD_DATE"."CAL_MONTH_NBR")+1)
	Missed Emergencies	CD_RESP_TM_DEV.SLA_STATE_DESCR = 'Missed'
	Missed Appointments	SUM(CF_FLD_ACTIVITY.FACT_CNT) where CF_FLD_ACTIVITY.APPOINTMENT_IND=1 and CD_APPT_TM.APPT_STATUS_CD = 'M1MS'
	Completed Activity Count	Sum(case when CD_TASK_BO_STATUS.INCOMPLETE_IND =0 and CD_TASK_BO_STATUS.STATUS_CD='COMPLETED' then CF_FLD_ACTIVITY.FACT_CNT else 0 end) Join with Status_date_key from Cd_date

Field	OBIEE Field	Load
	Count	sum(CF_FLD_ACTIVITY.FACT_CNT) Number Of Emergencies: SUM(CF_FLD_ACTIVITY.FACT_CNT) where EMERGENCY_IND=1
	Emergency%	("Core"."CF_FLD_ACTIVITY"."EMERGENCY_COUNT" / "Core"."CF_FLD_ACTIVITY"."FACT_CNT")*100
	Incomplete Activities	CASE WHEN "Core"."CD_TASK_BO_STATUS"."INCOMPLETE_IND" = 1 THEN "Core"."CF_FLD_ACTIVITY"."TOT_ACTIVITY_CNT" ELSE 0 END
	Incomplete Activities %	((("Core"."CF_FLD_ACTIVITY"."INCOMPLETE_ACTIVITY_CNT") * 100) / ("Core"."CF_FLD_ACTIVITY"."TOT_ACTIVITY_CNT")
	Missed Appointments	Filter("Core"."CF_FLD_ACTIVITY"."TOT_ACTIVITY_CNT" Using "Core"."CD_RESP_TM_DEV"."SLA_STATUS_CD" = 'M1MS')
	%Missed	CAST("Core"."CF_FLD_ACTIVITY"."MISSED_SUM" * 100 AS FLOAT) / ("Core"."CF_FLD_ACTIVITY"."TOT_ACTIVITY_CNT")
	Average Emergencies %	("Core"."CF_FLD_ACTIVITY"."EMERGENCY_IND_SUM") * 100) / ("Core"."CF_FLD_ACTIVITY"."TOT_ACTIVITY_CNT")
	Response Time	"Core"."CF_FLD_ACTIVITY"."TOT_RESP_DUR" / "Core"."CF_FLD_ACTIVITY"."TOT_ACTIVITY_CNT"
	Scheduled	sum(CF_FLD_ACTIVITY.APPOINTMENT_IND)
	Closed	filter("Core"."CF_FLD_ACTIVITY"."SCHEDULED_APPOINTMENT" using ("Core"."CD_TASK_BO_STATUS"."INCOMPLETE_IND" =0 and "Core"."CD_TASK_BO_STATUS"."STATUS_CD" = 'COMPLETED'))
	Average	Cast("Core"."CF_FLD_ACTIVITY"."CLOSED_APPOINTMENT"/ 15 AS FLOAT)
	Close Rate %	("Core"."CF_FLD_ACTIVITY"."CLOSED_APPOINTMENT" *100/ ("Core"."CF_FLD_ACTIVITY"."SCHEDULED_APPOINTMENT"))

Field	OBIEE Field	Load
	Late	Filter("Core"."CF_FLD_ACTIVITY"."APPT_IND_SUM" Using "Core"."CD_APPT_TM"."APPT_STATUS_CD" = 'M1MS')
	% of Total	(CAST ("Core"."CF_FLD_ACTIVITY"."LATE_APPOINTMENT" * 100 as FLOAT)/ "Core"."CF_FLD_ACTIVITY"."APPT_IND_SUM")
	Number of Appointments	sum(CF_FLD_ACTIVITY.APPOINTMENT_IND)
	Number of Activities	Filter("Core"."CF_FLD_ACTIVITY"."TOT_ACTIVITY_CNT" Using "Core"."CF_FLD_ACTIVITY"."WORK_ATTEMPT_CNT" > 1)
	Number of Canceled Activities	Filter("Core"."CF_FLD_ACTIVITY"."TOT_ACTIVITY_CNT" Using "Core"."CD_TASK_BO_STATUS"."STATUS_CD" = 'CANCELED')
	% Canceled	("Core"."CF_FLD_ACTIVITY"."CANCELED_ACTIVITY_CNT" * 100) / "Core"."CF_FLD_ACTIVITY"."TOT_ACTIVITY_CNT"
	Number of Attempts	sum(CF_FLD_ACTIVITY.WORK_ATTEMPT_CNT)
	Average Response Time	"Core"."CF_FLD_ACTIVITY"."TOT_RESP_DUR" / "Core"."CF_FLD_ACTIVITY"."EMERGENCY_IND_SUM"
	On-time Appointments	Filter("Core"."CF_FLD_ACTIVITY"."APPT_IND_SUM" Using "Core"."CD_APPT_TM"."APPT_STATUS_CD" = 'M1OT')