

Oracle® Retail Advanced Inventory Planning
Store Replenishment Planning User Guide
Release 13.0.2

December 2008

Copyright © 2008, Oracle. All rights reserved.

Primary Author: Melody Crowley

The Programs (which include both the software and documentation) contain proprietary information; they are provided under a license agreement containing restrictions on use and disclosure and are also protected by copyright, patent, and other intellectual and industrial property laws. Reverse engineering, disassembly, or decompilation of the Programs, except to the extent required to obtain interoperability with other independently created software or as specified by law, is prohibited.

The information contained in this document is subject to change without notice. If you find any problems in the documentation, please report them to us in writing. This document is not warranted to be error-free. Except as may be expressly permitted in your license agreement for these Programs, no part of these Programs may be reproduced or transmitted in any form or by any means, electronic or mechanical, for any purpose.

If the Programs are delivered to the United States Government or anyone licensing or using the Programs on behalf of the United States Government, the following notice is applicable:

U.S. GOVERNMENT RIGHTS Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the Programs, including documentation and technical data, shall be subject to the licensing restrictions set forth in the applicable Oracle license agreement, and, to the extent applicable, the additional rights set forth in FAR 52.227-19, Commercial Computer Software—Restricted Rights (June 1987). Oracle Corporation, 500 Oracle Parkway, Redwood City, CA 94065

The Programs are not intended for use in any nuclear, aviation, mass transit, medical, or other inherently dangerous applications. It shall be the licensee's responsibility to take all appropriate fail-safe, backup, redundancy and other measures to ensure the safe use of such applications if the Programs are used for such purposes, and we disclaim liability for any damages caused by such use of the Programs.

Oracle, JD Edwards, PeopleSoft, and Siebel are registered trademarks of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners.

The Programs may provide links to Web sites and access to content, products, and services from third parties. Oracle is not responsible for the availability of, or any content provided on, third-party Web sites. You bear all risks associated with the use of such content. If you choose to purchase any products or services from a third party, the relationship is directly between you and the third party. Oracle is not responsible for: (a) the quality of third-party products or services; or (b) fulfilling any of the terms of the agreement with the third party, including delivery of products or services and warranty obligations related to purchased products or services. Oracle is not responsible for any loss or damage of any sort that you may incur from dealing with any third party.

Value-Added Reseller (VAR) Language

Oracle Retail VAR Applications

The following restrictions and provisions only apply to the programs referred to in this section and licensed to you. You acknowledge that the programs may contain third party software (VAR applications) licensed to Oracle. Depending upon your product and its version number, the VAR applications may include:

- (i) the software component known as **ACUMATE** developed and licensed by Lucent Technologies Inc. of Murray Hill, New Jersey, to Oracle and imbedded in the Oracle Retail Predictive Application Server – Enterprise Engine, Oracle Retail Category Management, Oracle Retail Item Planning, Oracle Retail Merchandise Financial Planning, Oracle Retail Advanced Inventory Planning, Oracle Retail Demand Forecasting, Oracle Retail Regular Price Optimization, Oracle Retail Size Profile Optimization, Oracle Retail Replenishment Optimization applications.
- (ii) the **MicroStrategy** Components developed and licensed by MicroStrategy Services Corporation (MicroStrategy) of McLean, Virginia to Oracle and imbedded in the MicroStrategy for Oracle Retail Data Warehouse and MicroStrategy for Oracle Retail Planning & Optimization applications.
- (iii) the **SeeBeyond** component developed and licensed by Sun Microsystems, Inc. (Sun) of Santa Clara, California, to Oracle and imbedded in the Oracle Retail Integration Bus application.
- (iv) the **Wavelink** component developed and licensed by Wavelink Corporation (Wavelink) of Kirkland, Washington, to Oracle and imbedded in Oracle Retail Mobile Store Inventory Management.
- (v) the software component known as **Crystal Enterprise Professional and/or Crystal Reports Professional** licensed by SAP and imbedded in Oracle Retail Store Inventory Management.
- (vi) the software component known as **Access Via**TM licensed by Access Via of Seattle, Washington, and imbedded in Oracle Retail Signs and Oracle Retail Labels and Tags.
- (vii) the software component known as **Adobe Flex**TM licensed by Adobe Systems Incorporated of San Jose, California, and imbedded in Oracle Retail Promotion Planning & Optimization application.
- (viii) the software component known as **Style Report**TM developed and licensed by InetSoft Technology Corp. of Piscataway, New Jersey, to Oracle and imbedded in the Oracle Retail Value Chain Collaboration application.
- (ix) the software component known as **DataBeacon**TM developed and licensed by Cognos Incorporated of Ottawa, Ontario, Canada, to Oracle and imbedded in the Oracle Retail Value Chain Collaboration application.

You acknowledge and confirm that Oracle grants you use of only the object code of the VAR Applications. Oracle will not deliver source code to the VAR Applications to you. Notwithstanding any other term or condition of the agreement and this ordering document, you shall not cause or permit alteration of any VAR Applications. For purposes of this section, “alteration” refers to all alterations, translations, upgrades, enhancements, customizations or modifications of all or any portion of the VAR Applications including all reconfigurations, reassembly or reverse assembly, re-engineering or reverse engineering and recompilations or reverse compilations of the VAR Applications or any derivatives of the VAR Applications. You acknowledge that it shall be a breach of the agreement to utilize the relationship, and/or confidential information of the VAR Applications for purposes of competitive discovery.

The VAR Applications contain trade secrets of Oracle and Oracle’s licensors and Customer shall not attempt, cause, or permit the alteration, decompilation, reverse engineering, disassembly or other reduction of the VAR Applications to a human perceivable form. Oracle reserves the right to replace, with functional equivalent software, any of the VAR Applications in future releases of the applicable program.

Contents

Preface	ix
Audience	ix
Related Documents	ix
Customer Support	ix
Review Patch Documentation	ix
Oracle Retail Documentation on the Oracle Technology Network.....	x
Conventions	x
1 Introduction	1
Overview.....	1
Architectural Notes	3
RPAS User Interface Basics	3
Workbooks.....	3
Worksheets	4
Wizards.....	4
Business Process Overview	4
How SRP Fits into the AIP Product.....	4
Replenishment System Process	5
2 Implementing Store-Only Replenishment First	9
Approach to Data Setup	9
Types of AIP Implementation.....	10
Replenishing Stores-Only, Without Reconciliation.....	10
Replenishing Stores-Only, With Reconciliation.....	11
Full AIP: Replenishing All Locations with Reconciliation	13
3 SRP Navigation	15
Logging into SRP.....	15
Accessing Help	16
Opening an Existing Workbook.....	17
Creating a New Workbook	18
Saving a Workbook	19
Saving Options	20
Closing a Workbook	21
Deleting a Workbook.....	21
Logging Off of SRP.....	22
What's Next.....	22
4 Workbook and Worksheet Descriptions	23
Global Domains	23
Low Variability Measures.....	23
SRP Administration Workbook	25
SRP Administration Wizard	26
SRP Global Parameters (Dept) Tab.....	28
SRP Default Parameters (Sub-Class/Store Format) Tab.....	37
SRP Alert Maintenance Workbook.....	45
SRP Alert Maintenance Wizard.....	46
SRP Alert Global Default (Sub-Class/Company) Tab.....	49
SRP Alert Default (SKU/Company) Tab.....	55
SRP Alert Exception (SKU/Store) Tab.....	59
Run Masks Tab.....	62
Alert Masks Tab	63

SRP by Source Distribution Review Workbook	64
SRP by Source Distribution Review Wizard	64
Distribution Review Tab	68
SRP Evaluation Workbook	71
SRP Evaluation Wizard	71
SRP Replenishment Plan Tab	77
SRP Exception Summary Tab	100
SRP Overstock Alert Summary Tab	103
SRP Interactive Evaluation Workbook	105
SRP Interactive Evaluation Wizard	107
SRP Replenishment Plan Tab	112
SRP Exception Summary Tab	143
SRP Overstock Alert Summary Tab	146
SRP Maintenance Workbook	148
SRP Maintenance Wizard	149
SRP Exception Parameters (SKU/Store/Day) Tab	152
SRP Exception Parameters (SKU/Store) Tab	162
SRP Exception Parameters (SKU/Store/Week) Tab	163
SRP Exception Parameters (SKU) Tab	164
SRP Implementation Parameters Workbook	166
SRP Implementation Parameters Worksheet	166
SRP Inventory Capping Parameters Workbook	169
Available Departments	169
Available Stores	170
Available Days	171
Inventory Capping Parameters (Subclass) Worksheet	172
Inventory Capping Parameters (SKU) Worksheet	173
Department Capacity Worksheet	174
SRP Inventory Capping Management Workbook	176
Available Departments	176
Available Stores	178
Available Days	179
Inventory Caps Tab	180
Inventory Caps Parameters Tab	184
SRP Apply Inventory Capping Workbook	185
Apply SKU Cap	185
SRP Presentation Stock Calculations Workbook	186
SRP Store Presentation Stock Calculations Wizard	186
Store Presentation Stock Calculations (SKU/Store/Day) Tab	189
USA Workbooks	192
USA Business Process	193
USA Replacement, Additive, and Delivery Window Workbook	193
USA Allocation on Dynamic Rule Based Index Workbook	204
USA Create Rule Based Index Workbook	217
USA Allocation on Rule Based Index Workbook	221
USA Create Store Based Index Workbook	231
USA Allocation on Store Based Index Workbook	239
Delete USA Workbook	250
5 Build Workbooks	257
Set Up Workbooks for Automatic Builds	257
Build a Workbook Manually	258
Build Manual Workbook	258

6	Calculations.....	259
	Replenishment	259
	Replenishment Calculations Variables	260
	Fixed Period.....	260
	ATP Dates.....	260
	Review Time.....	260
	Forecasted Demand over Review Time	260
	Customer Orders over Review Time	261
	Expected Receipts over Review Time	261
	Product Life	262
	Expected Spoilage	262
	Inventory Capping and Store Available Space	262
	Allocation Boundaries	264
	Allocation Boundaries Calculations Variables	264
	Replenishment Methods Used in SRP	267
	Min/Max Replenishment Method.....	267
	Time Supply Replenishment Method	270
	Dynamic Replenishment Method	274
	Hybrid Replenishment Method.....	278
	No Replenishment Method	282
	Poisson Replenishment Method.....	282
	Loaded SS Dynamic Replenishment Method	286
	Sales Week Range Replenishment Method	289
	Factor AWS Replenishment Method.....	292
	Calculate an Unconstrained Receipt Plan	295
	Current Inventory and Projected Inventory	295
	Net Inventory	296
	Calculate Ideal Receipt Quantity	297
	Round Ideal Receipt Quantity.....	299
	Reconciliation	304
	Total Demand and Available Inventory.....	305
	Allocation Process	306
	Determine Active Zone.....	307
	Use Watershed Algorithm for Allocation	307
	Substitution	308
7	Review Alerts and Manage Exceptions	309
	SRP Alerts	309
	Historical Availability Alerts.....	310
	Projected Availability Alerts	318
	Other Alerts	322
	Reviewing and Managing SRP Alerts	323
	The Alert Manager.....	324
	Analyzing and Resolving Alerts Using the Alert Manager and SRP Workbooks	325
8	Loading and Maintaining Data.....	333
	Data Required	333
	Adding a New Store Using a Sister Store	334
	Adding a New SKU Using a Like SKU.....	334
	Glossary.....	335

Preface

The Oracle Retail Advanced Inventory Planning User Guide describes the application's user interface and how to navigate through it.

Audience

This document is intended for the users and administrators of Oracle Retail Advanced Inventory Planning. This may include merchandisers, buyers, and business analysts.

Related Documents

For more information, see the following documents in the Oracle Retail Advanced Inventory Planning Release 13.0.2 documentation set:

- *Oracle Retail Advanced Inventory Planning Release Notes*
- *Oracle Retail Advanced Inventory Planning Data Management Online Online Help*
- *Oracle Retail Advanced Inventory Planning Data Management Online User Guide*
- *Oracle Retail Advanced Inventory Planning Order Management Online Help*
- *Oracle Retail Advanced Inventory Planning Warehouse Replenishment Planning User Guide*
- *Oracle Retail Advanced Inventory Planning Data Model Volume 1 Oracle Database Data Model*
- *Oracle Retail Advanced Inventory Planning Data Model Volume 2 Measure Reference Guide*
- *Oracle Retail Advanced Inventory Planning Patch Installation Guide*
- *Oracle Retail Advanced Inventory Planning Operations Guide*
- *Oracle Retail Advanced Inventory Planning Implementation Guide*

Customer Support

To contact Oracle Customer Support, access My Oracle Support at the following URL:

<https://metalink.oracle.com>

When contacting Customer Support, please provide the following:

- Product version and program/module name
- Functional and technical description of the problem (include business impact)
- Detailed step-by-step instructions to re-create
- Exact error message received
- Screen shots of each step you take

Review Patch Documentation

If you are installing the application for the first time, you install either a base release (for example, 13.0) or a later patch release (for example, 13.0.2). If you are installing a software version other than the base release, be sure to read the documentation for each patch release (since the base release) before you begin installation. Patch documentation can contain critical information related to the base release and code changes that have been made since the base release.

Oracle Retail Documentation on the Oracle Technology Network

In addition to being packaged with each product release (on the base or patch level), all Oracle Retail documentation is available on the following Web site (with the exception of the Data Model which is only available with the release packaged code):

http://www.oracle.com/technology/documentation/oracle_retail.html

Documentation should be available on this Web site within a month after a product release. Note that documentation is always available with the packaged code on the release date.

Conventions

Navigate: This is a navigate statement. It tells you how to get to the start of the procedure and ends with a screen shot of the starting point and the statement “the Window Name window opens.”

Note: This is a note. It is used to call out information that is important, but not necessarily part of the procedure.


This is a code sample
It is used to display examples of code

A hyperlink appears like this.

Introduction

Overview

Oracle Retail Advanced Inventory Planning (AIP) is a suite of modules that are designed to manage the supply chain needs of large retailers. These supply chain needs range from interaction with their suppliers through various layers of warehouses down to individual stores and e-commerce sites. It couples time-phased replenishment and allocation algorithms to produce an actionable receipt plan over time. This is based on demand forecasts, replenishment parameters, and inventory availability at the numerous supply points within the supply chain.



AIP takes its place as one of several integrated applications within the Oracle Retail Suite. The suite allows a retailer to manage its supply chain from demand forecasting through to the generation of orders, which can then be shared with collaborative planning partners.

The larger process across the Oracle Retail Suites takes the following form:

1. Oracle Retail Demand Forecasting (RDF) provides a forecast of consumer demand. This is made available to AIP.
2. The AIP batch run produces an actionable receipt plan using replenishment parameters maintained inside AIP. Hierarchy and Inventory data is provided by a merchandising system such as RMS.
3. The receipt plan is then sent to the Order Management module within AIP where those orders that need to be actioned are formally-prepared for execution. This includes the assignment of an order number.
4. Order Management then submits the appropriate orders to the merchandising system where purchase orders and transfers will be communicated to other systems. These orders will be returned to AIP in subsequent batch runs as “on-orders” orders.
5. Sales forecasts and order plans can then be shared at the appropriate level with suppliers by using a CPFR product so that trading partners can prepare for the forthcoming orders.

At the core of the AIP batch process are five replenishment sub-processes. These sub-processes perform calculations on a set of loaded static and dynamic data using replenishment parameters to produce a replenishment receipt plan for all locations in the supply chain. This functionality differs from many existing replenishment solutions because it yields an actionable plan across time. This gives retailers the ability to project their demand at all levels of the supply chain and to share these projections with their suppliers whenever it is appropriate.

Key to producing an actionable receipt plan is the inclusion of known inventory constraints. This is achieved by performing the five replenishment sub-processes across all locations in the following order:

1. The Replenishment module generates an unconstrained receipt plan for the part of the planning horizon over which constraints will subsequently be applied. This part of the planning horizon is called the Fixed Period.
2. The Shortfall Reconciliation module applies inventory limitations over the fixed period, modifying the receipt plan where necessary.
3. The Substitution module attempts to use product substitutes to satisfy any shortage created by Shortfall Reconciliation within the fixed period.
4. The Stockless module increases orders within the fixed period where necessary to ensure that no warehouse is left with inventory of a stockless product and contractual obligations to order specific quantities of products from vendors are honored.
5. Finally, the Replenishment module is run for a second time for the remaining part of the Planning Horizon after the fixed period.

The resulting receipt plan is then exported to the Order Management module where Order Numbers are produced and the orders released to external systems. Following formal order generation, these quantities are fed back into the system and the plan is updated to account for these orders as expected receipts. This type of planning allows the retailer to identify potential supply chain problems before they arise so that stock-outs and excess inventory problems can be prevented or reduced.

The volume of the receipt plan produced by AIP is very large, so a minimum of user involvement is desired, but it must also be possible for super-users to change parameters and to see the effects of their changes quickly in order to avoid persistent costly supply chain problems. The system intends that these parameters will be managed principally by exception. Manage by exception means that not every SKU or warehouse is reviewed and/or updated on a regular basis. Items with exceptions – alerts- will be reviewed and updated if necessary.

The user interacts with the AIP system through a number of modules:

- Store Replenishment Planning (SRP) workbooks are used to maintain the replenishment characteristics for stores. These workbooks allow the user to analyze system output and perform what-if style analysis when replenishment parameters are changed.
- Warehouse Replenishment Planning (WRP) workbooks are used to maintain the replenishment characteristics for warehouses. These workbooks allow the user to analyze system output and perform what-if style analysis when replenishment parameters are changed.
- Data Management online (DMo) is used to maintain the supply chain and network flow information. This includes sourcing links and lead-times.
- Order Management (OM) gives the user visibility of order forecasts and previously-executed orders. It permits a range of modifications to previously executed, but not yet received, purchase orders.

Architectural Notes

The batch replenishment and workbook modules within the AIP Solution run from a common platform, which is called the Oracle Retail Predictive Application Server (RPAS). RPAS is a foundation that includes features, such as:

- Multidimensional databases
- Product, time, and business location hierarchies
- Aggregation and spreading of data
- Workbooks and worksheets for displaying and manipulating forecast data
- Wizards for creating and formatting workbooks and worksheets
- Menus, quick menus, and toolbars for working with forecast and sales data
- Exception management and user-friendly alerts

See the *RPAS User Guide* for more details.

RPAS User Interface Basics

Workbooks

A workbook is an easily viewed, easily manipulated multidimensional framework that is used to perform specific business functions, such as generating replenishment receipt plans and reviewing parameters. To present data, a workbook can contain any number of multidimensional spreadsheets, called worksheets, as well as graphical charts. These components work together to facilitate viewing and analysis of business functions.

Data in a workbook can be viewed at lower levels of detail or higher levels of aggregation. Different views are obtained by changing the path and/or level of data rollup. Data in a workbook can also be manipulated at any hierarchical level. If you modify data at an aggregate level, these changes are distributed down to the lower levels. The reverse is also true – if you modify data at a lower level in the hierarchy, the aggregates of the data reflect those changes.

Worksheets

Worksheets are multidimensional spreadsheets that are used to display workbook-specific information. Workbooks can include one or many worksheets. Worksheets can present data in the form of numbers in a grid, or these numeric data values can easily be converted to a graphical chart.

You can display the information in a worksheet in a variety of formats; which are generally by rotating, pivoting, and changing the data rollup. These processes are explained in detail in the *Oracle Retail Predictive Application Server (RPAS) Online Help*, which is available from the Help menu in SRP or the accompanying print version of the *RPAS User Guide*. You can easily change the presentation style of data in a worksheet. When data sets are moved around, their positions change. Data can be viewed at a very high level of detail, or data values can be quickly aggregated and viewed at summary levels. Furthermore, worksheets and parts of worksheets can easily be changed into charts, which facilitate the graphical viewing and analysis of data.

Wizards

When new workbooks are created, assistance in defining the nature of the information displayed is provided in the form of wizards. Wizards are pre-defined steps that walk the user through the data selections necessary to use/build each workbook. Wizards are also available to prompt the user for information regarding the definition of alerts, and user account management.

Business Process Overview

How SRP Fits into the AIP Product

While the SRP workbooks allow the user to interact with the AIP replenishment system from a store perspective, SRP does not exist in its own right as a batch process.


Instead, the actual process of producing a store replenishment plan is accomplished by the running of the five batch replenishment modules.

These five modules, actually just four because the Replenishment module is run twice, are process oriented – rather than being location specific. Instead of each module being focused on just stores or just warehouses, each one is performed for all appropriate nodes in the network.

When strung together, these batch modules produce a constrained receipt plan for all locations in the network. SRP simply provides a store-oriented mechanism for interacting with the receipt plan.

Replenishment System Process

AIP supports a basic business process for creating and releasing replenishment plans for all locations in the network. This process combines batch and interactive online activities as depicted in the diagram below.



Business Process Workflow

Step 1 – Load and Maintain Data

To generate a constrained replenishment plan for any location, four main types of data must first be loaded into the RPAS database:

- Basic hierarchy and attribute information.
- Forecast Store Sales.
- Inventory information, including on-hand and in-transit information that has previously been created by AIP.
- Supply chain definition data including release and placement schedules, and sourcing links.

Step 2 – Perform Replenishment (in the fixed period)

Replenishment is run for the fixed period. The fixed period refers to the first part of the Planning Horizon in which inventory limitations apply. Replenishment is a destination-centric process. It addresses every node in the supply chain, starting with stores and progressing onto warehouses, identifying the unconstrained orders required within the fixed period for every SKU-pack/destination combination.

The orders for each SKU pack/destination combination are calculated over the fixed period using the latest inventory position, on-orders and in-transit information. Forecast sales represent demand on a store. For a warehouse however, the demand stream is determined by aggregating the orders of the stores served by the warehouse. These store orders are the ones created by this process step. This means that replenishment for stores is performed before replenishment for warehouses.

For each destination, the available information is used to make projections of future inventory positions for each delivery opportunity. If the projection for a delivery opportunity falls below boundaries dictated by the replenishment method, then an order is required. Each order is then subject to rounding.

The resulting orders represent the unconstrained receipt plan within the fixed period.

Step 3 – Perform Shortfall Reconciliation (in the fixed period)

Shortfall reconciliation takes the unconstrained receipt plan and applies inventory limitations. This process is source-centric and therefore works from top to bottom through the nodes in the supply chain network.

Shortfall Reconciliation compares the demands upon a source (aggregated destination orders) with the projected available inventory at the source. Availability is only projected for warehouses and vendors with Fixed Purchase Quantity agreements and therefore, Shortfall Reconciliation is only performed for these sources.

Where there is sufficient availability to meet demand, no changes are made to the orders. Where the availability at a source is less than the aggregated demand, Shortfall Reconciliation makes use of a user-maintained matrix to determine how destination priority should be used when sharing inventory. Watershed algorithms are used to share inventory in an attempt to give destinations of the same priority an equal chance of meeting the demand placed upon them.

The resulting orders at this point represent a constrained receipt plan for the fixed period. This plan will need to be further modified to account for more constraints.

Step 4 –Perform Substitution (in the fixed period)

The aim of Substitution is to attempt to satisfy shortages at a warehouse using supplies of a suitable substitute. Substitution is a source-centric activity that is only performed at warehouses in an attempt to ensure a store's need is fully met. No attempt is made to perform substitution for warehouse orders that will be shorted due to insufficient inventory.

Substitution examines those situations at a warehouse where the unconstrained receipt plan in step 2 across stores is now less than the constrained receipt plan in step 3. The difference between the two represents a shortage. It then uses any spare inventory of a substitute to meet that need. Spare inventory is that which is not required to meet unconstrained demand. If there is insufficient supply of the substitute then the priority matrix and waterfall algorithms are again used to distribute what inventory there is.

If having used one substitute, a shortfall on the original demand still exists, the process can be repeated multiple times until either no shortage exists or all available substitutes are exhausted.

The resulting orders now represent a constrained receipt plan, some of which are orders of substitutes SKUs.

Step 5 – Perform Stockless (for the fixed period)

Stockless functionality identifies those situations where there is excess stock at a Source that needs to be consumed by the destinations served by the source. Stockless is a source-centric process and works for vendors with SPQs and warehouses with stockless products.

Stockless identifies excess stock at sources. Excess stock is defined as any remaining inventory of a stockless product at a warehouse not consumed by demand, or any residual inventory at a Vendor that the retailer is contractually committed to the order.

Stockless attempts to increase orders from the source to absorb the excess. The priority matrix, watershed and fairshare algorithms are used to ensure that destinations are fairly dealt with.

The resulting orders represent the final constrained receipt plan for the fixed period. The orders in the fixed period will not be changed any further within the current batch run.

Step 6 – Perform Replenishment (after the fixed period)

Once the constrained receipt plan has been determined for the fixed period, the projected inventory position at the end of the fixed period can be calculated. This inventory position is then used as the basis for a second run of the Replenishment module, but this time focusing on the remaining planning horizon after the fixed period.

Given that no inventory constraints are applied after the fixed period, running Replenishment after the fixed period is all that is required to produce a receipt plan for this period of time.

When concatenated, the constrained receipt plan from the fixed period and the receipt plan from the post fixed period form what is referred to as the constrained receipt plan for the planning horizon (although as already mentioned no constraints were applied to the post fixed period).

It is this receipt plan that can be viewed from a store perspective within SRP and a warehouse perspective within WRP.

Step 7 – Export Orders to Order Management (after the fixed period)

Once a constrained receipt plan has been produced, a subset of the orders is then sent to the Oracle Platform for processing by Order Management. This subset contains the following:

- All into store and into warehouse orders sourced from Vendors (Purchase Orders) across the entire planning horizon.
- All into warehouse orders sourced from other warehouses (Transfers) across the entire planning horizon.
- All into store orders sourced from warehouses (Transfers) with release dates that need to be shipped today.

Step 8 – Order Management Execution of Orders

Of the subset of orders exported to Order Management, those with a release date of today are given appropriate orders numbers. The Order Numbers are allotted based upon an implementation-time mask that determines how orders (both Transfers and Purchase Orders) should be grouped together.

Those orders that have been allotted numbers are then executed (released) to the merchandising system for subsequent communication to other systems including EDI.

The Order Management GUI gives the user access to those orders that have already been released. Those purchase orders that have not been received may be updated. Those forecast Purchase Orders that have not yet been released because they ship at a later date may be executed early.

Implementing Store-Only Replenishment First

Clients may choose a phased implementation approach to AIP in order to mitigate supply chain management risks. The supported approach is to first replace the legacy Store Replenishment Process with AIP. Once stability has been achieved, the footprint of the implementation can then be expanded to cover the Warehouse Replenishment process.

The purpose of this section is to outline the special considerations that should be given to a phased AIP implementation. There are several stages of such an implementation, ranging from the most basic Store Replenishment, with no Reconciliation, to performing Replenishment across the entire supply chain with Reconciliation between all nodes. Each stage will be subsequently described and the key considerations identified. Note that the minimal required data is not a comprehensive list of every parameter required to make AIP run, simply a list of those parameters that require particular attention. First, however, a general approach to AIP Data Set up must be adopted.

Approach to Data Setup

With most systems, the quality of the output is directly related to the quality of the input data. This is especially true of AIP; for example, inaccurate data could produce orders for days where the destination is not open to receive them, or where the vendor does not ship.

An integrated supply chain product, AIP has been designed from the outset to keep replenishment planning activities across stores and warehouses consistent. Hence, the biggest benefits of AIP can really only be enjoyed when a full and accurate supply chain has been defined. For stores, this means that the into-warehouse supply chain should also been defined.

The most basic of Replenishment activities for the store does not need the warehouse supply chain above it to be accurately defined. However, given the design of the AIP Automation logic, if there is any intent to implement Reconciliation activities between the Warehouse and Store levels, or to Replenish Warehouses, then a full top to bottom supply chain should be defined from the outset.

The choice to turn off Automation either in part or completely should not be undertaken lightly. The driver for the Automation logic is the receipt of a new piece of reference data from an external system. Once the first day for that new piece of data has passed, any opportunity to use Automation to set up any part of the supply chain relating to the new data has also passed. Turning on Automation or some of its various elements will not retroactively “fill in the pieces.” Therefore, if Reconciliation is turned off, the user can only manually provide the missing data.

For this reason, it is highly recommended that the GA Automation Logic be used in its entirety from the beginning. All the implementations described in the next section assume that Automation is turned on in its entirety from the outset.

Types of AIP Implementation

Replenishing Stores-Only, Without Reconciliation

Implementation Characteristics & Considerations

This is the most basic AIP implementation. AIP is responsible for replenishing stores without ever considering the availability of inventory in the warehouses servicing those stores. As such, the major consideration here is the accuracy of the into-store supply chain and replenishment methods.

Key Data Requirements

	Minimal Data Requirement	Details
DM Online - Screens	Full into-store supply chain	- SKU should be on sale and on supply at store. - SKU should be in a profile with an associated store order cycle. - Store source should be set. - SKU should have a preferred ordering packsize.
	Partial into-warehouse supply chain	- SKU-packs should be ranged to warehouses that will act as sources for stores. - Pallet Multiples into warehouses must be specified if pallet ordering by stores is required.
	Warehouse Reconciliation Setting	Reconciliation must be turned off for all SKU types for all warehouse locations.
RPAS Workbooks	Store Replenishment Methods Specified (And Associated Parameters)	- Replenishment methods for all SKU/Stores should be specified with all associated parameters. - Default settings should be specified in the SRP Admin Workbook. - Exceptions can be specified in the SRP Maintenance Workbook.
	Warehouse Replenishment Method Set to No Replenishment	This is only required if a full into-warehouse supply chain has been specified (either manually or by automation). In this instance, setting "No Replenishment" as a default method in the WRP Admin Workbook ensures that no warehouse replenishment planning is performed.
External Interface	Store Inventory, On-orders and In-transits	These are assumed to originate from RMS and are required to accurately project the inventory levels at stores.

Replenishing Stores-Only, With Reconciliation

Implementation Characteristics & Considerations

From a functional perspective, the only difference between running the most basic Store only implementation and running this scenario is turning Reconciliation on. However, this mode of operation requires an almost complete into-warehouse supply chain to be set up. It is assumed that another system other than AIP is responsible for replenishing the warehouses. Therefore, the warehouse replenishment methods should be set to “No Replenishment”.

Reconciliation will limit the warehouse-to-store transfers based upon the current and future projected warehouse inventory. This requires that external systems feed AIP all expected receipts (On-orders and In-transits) into warehouse as well as the current warehouse inventory.

Reconciliation as a process runs over the fixed period. The Fixed Period for a destination, such as a store, is based upon the sum of lead times between all the nodes that inventory must pass through in order to get to the destination (assuming there is no delay in a warehouse between a product being received and becoming available to meet demand). In a situation where it takes ten days to get inventory from a vendor to a warehouse, and a further five days to get that inventory from the warehouse to the store, the fixed period is determined as fourteen days (combined lead times of ten and five days minus one day). Any order into the store in the first fourteen days must come from either existing warehouse inventory or expected receipts into the warehouse that cannot be changed. Any into store transfer will be reduced or cut if there is insufficient current or future inventory in the warehouse.

The value proposition of Reconciliation is therefore dependent upon the accuracy and consistency of the following two pieces of information:

- The calculated Fixed Period.
- The horizon over which expected receipts are passed to AIP.

The calculation of the Fixed Period is entirely dependent upon the into-warehouse and store supply chains. The supply chain definitions must be accurate if an appropriate Fixed Period is to be determined. A complete picture of expected receipts over the Fixed Period is also required. An incomplete set of expected receipts would lead to the inventory picture over the Fixed Period being understated and store orders being reduced or cut unnecessarily.

Passing Expected Receipts over a greater time period than the Fixed Period does not cause any harm. Neither does overstating the Fixed Period, as long as there is genuinely a full picture of expected Receipts to accompany the longer period.

Key Data Requirements

	Minimal Data Requirement	Details
DM Online - Screens	Full Into-Store Supply Chain	- SKU should be on sale and on supply at the store. - SKU should be in a profile with an associated store order cycle. - Store source should be set. - SKU should have a preferred ordering packsize.
	Almost Complete Into-Warehouse Supply Chain (No Warehouse Order Multiple Required)	- SKU-packs should be ranged to warehouses that will act as sources for stores. - SKUs should be assigned Order and Delivery Groups (assignment performed at the Demand Group level). - Into-warehouse source splits must be specified. - A warehouse location orderable unit must be specified for each source with a positive split percentage. - Pallet Multiples into warehouses must be specified if pallet ordering by stores is required, but are not required as warehouses are not being replenished. - Order Multiples into warehouses need not be specified as warehouses if they are not being replenished by AIP.
	Warehouse Reconciliation Setting	Reconciliation must be turned on for appropriate SKU types at all warehouse locations.
RPAS Workbooks	Store Replenishment Methods Specified (And Associated Parameters)	- Replenishment methods for all SKU/Stores should be specified with all associated parameters. - Default settings should be specified in the SRP Admin Workbook. - Exceptions can be specified in the SRP Maintenance Workbook.
	Warehouse Replenishment Method Set To No Replenishment	This is only required if a full into-warehouse supply chain has been specified (either manually or by automation). In this instance, setting "No Replenishment" as a default method in the WRP Admin Workbook ensures that no warehouse replenishment planning is performed.
External Interface	Store Inventory, On-orders and In-transits	These are assumed to originate from RMS and are required to accurately project the inventory levels at stores.
	Warehouse Inventory, On-orders and In-transits	While AIP is not generating orders into warehouse, AIP does require this information to properly project the availability of inventory in the warehouse against which store orders will be reconciled.

Full AIP: Replenishing All Locations with Reconciliation

Implementation Characteristics & Considerations

This is the full AIP implementation. Warehouse Order Multiple and Warehouse Replenishment methods and associated parameters are the only additional requirements over the previous implementation. At the point of full implementation, AIP will be mastering all orders into all locations, and expects all such orders to be fed back as On-orders and In-transits.

Key Data Requirements


	Minimal Data Requirement	Detail
DM Online - Screens	Full Into-Store Supply Chain	- SKU should be on sale and on supply at store. - SKU should be in a profile with an associated store order cycle. - Store source should be set. - SKU should have a preferred ordering pack size.
	Full Into-Warehouse Supply Chain	- SKU-packs should be ranged to warehouses that will act as sources for stores. - SKUs should be assigned Order and Delivery Groups (assignment performed at the Demand Group level). - Into-warehouse source splits must be specified. - Warehouse location orderable unit must be specified for each source with a positive split percentage. - Order Multiple for each Warehouse location orderable unit must be specified. - Pallet Multiples into warehouses must be specified if pallet ordering by stores is required, but are not required as warehouses are not being replenished.
	Warehouse Reconciliation Setting	Reconciliation must be turned on for appropriate SKU types at all warehouse locations.
RPAS Workbooks	Store Replenishment Methods Specified (And Associated Parameters)	- Replenishment methods for all SKU/Stores should be specified with all associated parameters. - Default settings should be specified in the SRP Admin Workbook. - Exceptions can be specified in the SRP Maintenance Workbook.
	Warehouse Replenishment Methods Specified (And Associated Parameters)	- Replenishment methods for all SKU/Warehouses should be specified with all associated parameters. - Default settings should be specified in the WRP Admin Workbook. - Exceptions can be specified in the WRP Maintenance Workbook.
External Interface	Store Inventory, On-orders and In-transits	These are assumed to originate from RMS and are required to accurately project the inventory levels at stores.
	Warehouse Inventory, On-orders and In-transits	These are assumed to originate from RMS and are required to accurately project the inventory levels at warehouses.

SRP Navigation

This chapter provides a brief description of how to get started using SRP.

Logging into SRP


1. From the Windows Start menu, select **Programs – Oracle Predictive Solutions – Oracle Predictive Solutions**. The Login Information dialog box appears.



Login Information Dialog

2. Enter your User Name and your Password in their respective fields.
3. Click **Login**.

After you successfully log in as an SRP user, a window is displayed with the following menu bar and toolbar.




Oracle Predictive Solutions [AIP 12] Main Menu and Toolbar – No Workbooks Open

Accessing Help

The Oracle Retail Predictive Solutions Help provides information that is common to the use of all Retail Predictive Solutions products. It includes general topics; such as Basic RPAS Concepts, Using Workbooks, Worksheets, and Wizards, Changing Views of Data in Worksheets, and Using Special RPAS Features. Material in online Help is replicated in the *RPAS User Guide* for offline access. Information that is specific to SRP is provided in this user guide as outlined in the table of contents.

To become familiar with workbooks and worksheets, different data views, and other general topics, open the Help and review the topics that are available. For example, for details on all of the menu options and toolbar buttons, follow this procedure:

1. From the main menu, select **Help – Contents** (or press F1). Your Web browser opens and displays the Help window.
2. Within the Help window, select **Basic RPAS Concepts – Menus, Quick Menus, and Toolbars**. Select an applicable topic.




Help Contents – Menus, Quick Menus, and Toolbar Topic

Opening an Existing Workbook

If SRP workbooks have already been created, a list of the workbooks that are available to the user can be displayed and selected.

1. Select **File – Open**, or click the **Open** button on the toolbar.

The Open window appears. This window provides lists of all workbooks that were previously created.



Open Workbooks Window


2. Select a workbook to read or edit.
3. Click **OK**. The selected workbook is opened. The last visible window when the workbook was saved is displayed. Use the next or previous arrows to navigate through the workbook windows.

Creating a New Workbook

Choose New from the File menu, or click **New**. This launches wizards to provide a step-by-step method for creating new workbooks.

Note: This procedure outlines the basic steps for creating a new workbook. For detailed information about building specific SRP workbooks, see “Chapter 3 – Workbook and Worksheet Descriptions”.

1. From the main menu, select File – New, or click **New**. The New dialog box appears.




“New” Window for Creating Workbooks

2. Click the SRP tab. This tab contains workbook templates for each workbook type.
3. Click on the workbook template for the workbook type that you want to build.
4. Click **OK**.
5. Follow the wizard instructions to create the workbook.

Saving a Workbook

A newly created workbook can be saved at any point in the planning process and opened later to complete the planning process or edit previous steps. This action also allows flexibility to continuously revise plans as new information comes in.

1. From the File menu, select Save. The Save As dialog is displayed.



Save As Dialog for Workbooks

The column fields in the list box describe existing workbooks:

- Name – Name of workbook
- Owner – Name of owner
- Template Group – SRP
- User Group – Work group of the plan originator
- Type – Type of workbook
- Created – Date of origination
- Modified – Date of last update
- Access – User (originator), world or group access

The Save As window displays previously saved workbooks. The first field is blank. When a name is entered for this workbook, it is displayed in the list of workbook that can be viewed or edited. This workbook name is displayed on the title line when the workbook is open for further build or editing procedures.

2. Enter an identifying name in the top Workbooks field.

3. In the Save Access As section, select User, World, or Group. If Group is selected, other users within your group are allowed to view or edit this workbook. If User is selected, only the plan originator is allowed to view or edit this workbook. If World is selected, any user is allowed to view or edit this workbook.
4. If you want all workbooks from your group to be displayed for viewing or editing, select the List All Workbooks check box. If this check box is cleared, only the workbooks that were created by you as the Owner are displayed.
5. Click **OK**. The parameters of this workbook are saved and the workbook structure is available for continued planning or for access at another time.

Saving Options


The following options are available on the file menu.

Option	Description
Save	This option allows you to save all information in the workbook including the current layout of worksheets within the steps. This option has the same result as if you select File – Save, or if you click the Save button on this toolbar. The Save button updates the stored information if the current workbook was previously saved. If the workbook was not previously saved, the Save button produces the Save As dialog where you specify a workbook name. The Save button does not commit changes to the master database.
Commit Now	This option commits the current state of data in your workbook to the master database. This option has the same result as if you had selected File – Commit Now. If changes were made in the workbook since the last save, you are asked whether or not you want to save the workbook before committing your data.
Save and Commit Now	This option saves the workbook and immediately commits the data to the master database. Workbook information may be available for other users.
Save and Commit Later	This option immediately saves the workbook. At a later time, the workbook will be committed to the master database during a batch process when system utilization is minimized.

Closing a Workbook


1. From the File menu, select **Close**.

If changes were made to the workbook without selecting Calculate, the Calculate Workbook dialog box appears.



Calculate Workbook Dialog

2. Click **Yes** to retain changes and calculate, or **No** to ignore (discard) the changes. If 'Yes' is selected, the Close Workbook dialog box appears.



Close Workbook Dialog

3. Choose the commit type if desired and click **Save**, **Don't Save** (discard the changes) or **Cancel** to abort the process.

Deleting a Workbook

Choose Delete from the File menu, or click **Delete** to display a window that lists all of the plans and reports that were previously created. You can select a workbook for deletion.

1. From the File menu, select **Delete**, or click the Delete button on the toolbar. The Delete window, which shows a list of workbooks, appears.
2. Select the title of the workbook that you want to delete. The workbook title is highlighted.
3. Click **OK**. A dialog window prompts you to confirm your decision.
4. Click **OK** to delete the workbook, or click **Cancel** to abort the process.

Logging Off of SRP

Follow this procedure to log off of the system and immediately exit Oracle Predictive Solutions.

1. From the File menu, select **Exit**.
2. If changes were made to an open workbook, the same procedures are followed for closing a workbook without calculating.

Follow this procedure to log off of the system and to leave the Login dialog open for another user or for use with another Oracle Retail planning product.

1. From File menu, select **Logoff**.
2. If changes were made to an open workbook, the same procedures are followed for closing a workbook without calculating.

What's Next

Once you are familiar with the procedures in this chapter, you can explore the other features and functions of SRP as described in the remaining chapters of this user guide.

Workbook and Worksheet Descriptions

This section describes the standard workbooks, worksheets, and associated measures that are used within SRP. Information for each measure will be entered by the client based on the client's needs. This section also describes the differences between global domains and simple domains.

Global Domains

The SRP solution is always implemented on global domains. Global domains provide you with the ability to build, review, save, and commit workbooks in a master domain with data from multiple local domains.

Low Variability Measures

AIP employs the concept of low variability for several high-density measures. Low Variability measures are those which are time-phased by day and tend to change very little over time. Because there is little change, the same value is often repeated for several days. AIP takes advantage of this redundancy, by storing only changed values in low variability measures.

AIP also allows maintenance of replenishment parameters at various level of the product hierarchy to provide the user with the capability of creating settings, using overrides only for exceptions.

The user can maintain these parameters at three levels in the hierarchy:

- Global parameters are the highest default level used in determining the effective value of the measure. In other words, the parameter values at the global level will only be used if no lower level ((default or exception) parameters exist.
- Default Parameters are the second and middle default level used in determining the effective value of the measure. In other words, the parameter values at the default level will only be used if no lower level (exception) parameters exist. Parameter values at the Sub-class/Store Format level will be used over global defaults.
- Exception parameters are the lowest level used in determining the effective value of the measure. In other words, exception parameters will be used over global and default level parameters.
- The default parameters allow the user to enter parameters that will affect many SKUs. Defaults can be used to set up basic replenishment parameters to meet the objectives of the business, with exceptions used for override values. Many of the exception level parameters are also time-phased by day or week, allowing the user to change parameters prior to the actual date the change is effective.

At the exception level, when data is entered on a specific date, that date becomes an 'effective date' for that measure. Once a value is entered on a date, the value will remain in effect until the value is changed to another valid value, or a special value is entered. The special values are introduced for low variability measures to allow the user to enter an exception value only on the date it becomes effective, remove the exception value to set the parameter back to the default value, and to indicate the parameter has no upper boundary.

The special values are described in the table below.

Value	Description
-1 (Use Previous)	Indicates the measure will use the value from the previous day (i.e., the value remains the same as the prior day).
-2 (Use Default)	Indicates the measure will be set to its original default value from the global or default level.
-3 (Unbounded)	Indicates the measure is unbounded; it has no minimum or maximum limits.

Expanded measures show logical results of the multi-tiered defaults and low variability measures that are used in calculations.

The following example shows the results of a user entering data at the exception level.

Example: Max Time Supply Days has a global default value of 14 and no value at the default level.

Date	11/27	11/28	11/29	11/30	12/01	12/02
User Entered Value (exception level)		7			-2	
Expanded Results	14	7	7	7	14	14

The following example shows the results of an unbounded measure (Maximum Stock) with global, default and exception data. For this example, assume the global and default values change on the date indicated in the table below.

Date	11/27	11/28	11/29	11/30	12/01	12/02	12/03
Global	800	800	800	800	800	800	-3
Default	500	500	500	500	-3	-2	-1
Exception	-3	-1	-1	-2	-1	-1	-1
Expanded Results	∞	∞	∞	500	∞	800	∞

Based on this example:

- On 11/27, the user enters '-3' at the exception level, indicating that there is no upper limit for Maximum Stock.
- On 11/28 and 11/29, nothing is entered at the exception level. The default value of '-1' indicates the previous value will be used, resulting in Maximum Stock remaining unbounded.
- On 11/30, the user enters '-2' at the exception level, indicating the default value will be used, resulting in Maximum Stock of 500 (default level).
- On 12/01, nothing is entered at the exception level. The default value of '-1' indicates the previous value (default level) will be used. The default level has changed to '-3', resulting in Maximum Stock being unbounded.

- On 12/02, nothing is entered at the exception level. The default value of '-1' indicates the previous value will be used. The default level has changed to '-2', indicating the global default value will be used, resulting in Maximum Stock of 800 (global level).
- On 12/03, nothing is entered at the exception level. The default value of '-1' indicates the previous value (global level) will be used. The global default level has changed to '-3', resulting in Maximum Stock being unbounded.

SRP Administration Workbook


The SRP Administration workbook is used to set up the global (dept) and default (sub-class/store format) values that are used to populate measures when no exception (SKU/store/day) value exists. The values set here define the details of the replenishment method used and are used to generate a replenishment plan. SKU/store/day-specific parameter changes are made through the SRP Maintenance workbook. This workbook contains worksheets that are grouped into two tabs with the associated worksheets:

- SRP Global Parameters (Dept) tab
 - SRP Global Parameters (Dept)
- SRP Default Parameters (Sub-class/Store Format) tab
 - The SRP Default Parameters (Sub-class/Store Format)

SRP Administration Wizard

Available Departments


The dialog box for Available Departments displayed below will show a list of all Departments in the AIP domain. The user's previous selections are already selected. The user has the ability to re-select which Departments will be accessed in the workbook. The positions default to the Dept level. Standard RPAS functionality is available for this particular wizard page.



SRP Administration Wizard – Available Departments

Available Store Formats

The dialog box for Available Store Formats displayed below will show a list of all Store Formats in the AIP domain. The user's previous selections are already selected. The user has the ability to re-select which Store Formats will be accessed in the workbook. The positions default to the Store Format level. Standard RPAS functionality is available for this particular wizard page.

**SRP Administration Wizard – Available Store Formats**

When the user selects 'Finish', the workbook will be built using the Departments and Store Formats selected.

SRP Global Parameters (Dept) Tab

SRP Global Parameters (Dept) Worksheet

The SRP Global Parameters (Dept) worksheet contains the global department level default values for parameters that are used in generating and processing store replenishment plans.

The screenshot shows a software window titled "SRP Global Parameters (Dept)". At the top, there is a "Product" field and a "CALCULATOR/ORGANIZER" button with navigation icons. Below this is a table with 30 rows, each representing a global parameter. The parameters are listed in the first column, and the second column is for input. The parameters are:

Parameter Name	Value
Store Global Default AWS Factor	
Store Global Default Boundary Stock	
Store Global Default Demo Stock	
Store Global Default End Date Range	
Store Global Default Increment Percent	
Store Global Default Inventory Selling Days	
Store Global Default Max Safety Stock Days	
Store Global Default Max Safety Stock Units	
Store Global Default Max Stock	
Store Global Default Max Time Supply Days	
Store Global Default Min Safety Stock Days	
Store Global Default Min Safety Stock Units	
Store Global Default Min Stock	
Store Global Default Min Time Supply Days	
Store Global Default MSQ Constraint Indicator	
Store Global Default Percent of Pallet	
Store Global Default Promotion Presentation Stock Override Flag	
Store Global Default Repl Method	
Store Global Default Roll Weeks	
Store Global Default Rounding Method	
Store Global Default Rounding Threshold	
Store Global Default Safety Stock Level Factor	
Store Global Default Service Level	
Store Global Default Shelf Capacity	
Store Global Default Shelf Capacity Flag	
Store Global Default Start Date Range	
Store Global Default Time Supply Horizon	
Store Global Default Weekly Sales Max	
Store Global Default Weekly Sales Min	
User Specified Store Global Default Presentation Stock	

At the bottom of the window, there is a "Measure" field with a dropdown arrow and a "Measure" button.

SRP Global Parameters (Dept) Worksheet

The SRP Global Parameters (Dept) worksheet contains writeable measures at the department level.

The following measures appear automatically when using the default template.

Measure Label	Description
Store Global Default AWS Factor	The AWS Factor allows SRP users to provide a numeric factor to be multiplied against the average weekly sales (AWS) to determine replenishment boundaries (safety stock, receipt point and receive up to level) for the Factor AWS replenishment method. Any positive number is valid. Example: To calculate a safety stock that is 50% of the average weekly sales, the user would enter an AWS Factor of .5.
Store Global Default Boundary Stock	The Boundary Stock identifier allows SRP users to select the stock level to use in calculating the Store Receipt Point and Store Receive Up to Level. This stock level is a combination of Safety Stock, Presentation Stock and/or Promotional Presentation Stock based on the identifiers listed below. If the identifier contains “vs”, the greater value will be used. This parameter affects all replenishment methods. The user selects the boundary stock identifier from the following Picklist options: ▪ SS vs PS + PPS ▪ SS vs PS ▪ SS vs PPS ▪ SS + PS + PPS ▪ SS + PS ▪ SS + PPS ▪ SS Where, SS = Safety Stock PS = Presentation Stock PPS = Promotional Presentation Stock The picklist default is SS vs PS + PPS. Example: Selecting SS vs PS will add the greater of SS or PS to the calculated Store Receipt Point and Store Receive Up to Level values.
Store Global Default Demo Stock	Amount of stock that is used as demonstration product, but is still available to sell. Demo Stock is added to the RP and RUTL levels for each day.
Store Global Default End Date Range	The End Date Range parameter allows SRP users to select the date that should be used as the ending point for determining the historical sales data used by the “Sales Date Range” and “Factor AWS” replenishment methods. A pop-up calendar can be used to select the desired end date. Select a date less than or equal to the current date.
Store Global Default Increment Percent	The Increment Percent acts as a multiplier for minimum and maximum stock that is designed to handle temporary fluctuation in demand for items using Min/Max Replenishment Method. An increment percentage factor can be used to temporarily increase or decrease targeted stocking levels without altering the established MIN and MAX values. Any positive number, including zero, is valid. Example: To use 120% of the Min and Max Stock, the user would enter an Increment Percent of 1.2.

Measure Label	Description
Store Global Default Inventory Selling Days	The Inventory Selling Days parameter is used to specify the number of days of forecast quantity to be used when calculating the Receive up to Level (RUTL) with the Hybrid, Dynamic, Poisson and Loaded SS Dynamic Replenishment Methods. The RUTL calculation will use the forecast demand over the greater of Inventory Selling Days and Review Time. Inventory Selling Days can be used to avoid producing very small frequent orders. Any positive integer, including zero, is valid. Example: To ensure an order will contain at least 14 days of supply, 14 would be entered as the number of Inventory Selling Days.
Store Global Default Max Safety Stock Days	The Max Safety Stock Days parameter is used to specify the maximum number of days of cover to be kept on hand as safety stock. If the user enters both Max Safety Stock Days and Max Safety Stock Units, the maximum safety stock boundary will use the larger of demand over max safety stock days and max safety stock units. Any positive integer, including zero, is valid. Example: To ensure the maximum safety stock will contain at least 14 days of supply, 14 would be entered in Max Safety Stock Days. If Max Safety Stock Units is greater than 14 days of supply, max units would be used as the maximum safety stock, otherwise maximum safety stock would be the number of units required to cover 14 days of demand, calculated as the sum of demand over the next 14 days beginning with the current day.
Store Global Default Max Safety Stock Units	The Max Safety Stock Units parameter is used to specify the maximum amount of inventory to be kept on hand as safety stock. If the user enters both Max Safety Stock Days and Max Safety Stock Units, the maximum safety stock boundary will use the larger of demand over max safety stock days and max safety stock units. Any positive number, including zero, is valid. Example: To ensure the maximum safety stock will contain at least 14 days of supply, 14 would be entered in Max Safety Stock Days. If Max Safety Stock Units is greater than 14 days of supply, max units would be used as the maximum safety stock, otherwise maximum safety stock would be the number of units required to cover 14 days of demand.
Store Global Default Max Stock	Max Stock is only used in the Min/Max Replenishment Method. It represents the maximum stock level in units that are desired on hand to satisfy demand. The receipt plan quantity is calculated to bring Net Inventory up to MAX. Any positive number, including zero, is valid.
Store Global Default Max Time Supply Days	Max Time Supply Days is only used in the Time Supply Replenishment Method. It represents maximum stock level in terms of number of days cover that that are desired on hand to satisfy demand. The receipt plan quantity is calculated to bring Net Inventory up to Maximum Time Supply Days of cover. Any positive integer, including zero, is valid. Example: To ensure an order will bring the inventory level up to 14 days of supply, 14 would be entered in Max Time Supply Days.

Measure Label	Description
Store Global Default Min Safety Stock Days	The Min Safety Stock Days parameter is used to specify the minimum number of days of cover to be kept on hand as safety stock. If the user enters both Min Safety Stock Days and Min Safety Stock Units, the minimum safety stock boundary will use the larger of demand over min safety stock days and min safety stock units. Any positive integer, including zero, is valid. Example: To ensure the minimum safety stock will contain at least 7 days of supply, 7 would be entered in Min Safety Stock Days. If Min Safety Stock Units is greater than 7 days of supply, min units would be used as the minimum safety stock, otherwise minimum safety stock would be the number of units required to cover 7 days of demand, calculated as the sum of demand over the next 7 days beginning with the current day.
Store Global Default Min Safety Stock Units	The Min Safety Stock Units parameter is used to specify the minimum amount of inventory to be kept on hand as safety stock. If the user enters both Min Safety Stock Days and Min Safety Stock Units, the minimum safety stock boundary will use the larger of demand over min safety stock days and min safety stock units. Any positive number, including zero, is valid. Example: To ensure the minimum safety stock will contain at least 7 days of supply, 7 would be entered in Min Safety Stock Days. If Min Safety Stock Units is greater than 7 days of supply, min units would be used as the minimum safety stock, otherwise minimum safety stock would be the number of units required to cover 7 days of demand.
Store Global Default Min Stock	Min Stock is only used in the Min/Max Replenishment Method. It represents the minimum stock level in units that are desired on hand to satisfy demand. Min Stock is used in determining the inventory level at which a replenishment is triggered. Any positive number, including zero, is valid.
Store Global Default Min Time Supply Days	Min Time Supply Days is only used in the Time Supply and Hybrid Replenishment Method. It represents minimum stock level in terms of number of days cover that that are desired on hand to satisfy demand. Min Time Supply Days of cover is used in both safety stock and receipt point calculations. Any positive integer, including zero, is valid. Example: To ensure a minimum inventory level that will cover 7 days of supply, 7 would be entered in Min Time Supply Days.
Store Global Default MSQ Constraint Indicator	The Store Global Default MSQ Constraint Indicator indicates when the MSQ should be applied as a constraint during ordering decisions. If unspecified, the indicator is considered to be 'On' and MSQ will be used as a constraint.

Measure Label	Description
Store Global Default Percent of Pallet	Percent of pallet is used to determine if the Ideal Receipt Quantity for replenishment should be rounded to a full pallet. It represents the percentage threshold that case demand must exceed in order for pallet rounding to occur. Valid values are 0 through 1. While zero (0) is a valid value, it indicates that the ideal receipt quantity will not be rounded by pallet. Example: If an SRP user wants to round an order up to a pallet if the case demand is greater than 75 percent of a pallet, the user would enter .75 in Percent of Pallet.
Store Global Default Promotion Presentation Stock Override Flag	The Store Global Default Promotion Presentation Stock Override Flag indicates what value should be used for Store Promotion Presentation Stock. When the override flag is turned on ("TRUE"), the Store Promotion Presentation Stock equals zero (0).
Store Global Default Repl Method	The choice of Replenishment Method determines the type of calculations that will be used in generating a store replenishment method. The user selects the Replenishment Method from the following picklist options: ▪ Min/Max ▪ Time Supply ▪ Dynamic ▪ Hybrid ▪ No Replenishment ▪ Poisson Replenishment ▪ Loaded SS Dynamic ▪ Sales Week Range ▪ Factor AWS The picklist default is No Replenishment
Store Global Default Roll Weeks	The Roll Weeks parameter indicates whether SRP logic should automatically roll the start and end date range settings forward one week or not. Roll weeks is used in the Factor AWS Sales Date Range Replenishment Methods. The user selects the Roll Weeks value from the following picklist options: ▪ Yes ▪ No ▪ Default Example: Selecting 'Yes' will cause the start and end date to roll forward one week, allowing the user to keep the weekly historical sales at the same relative distance in the past. Selecting 'No' will not move the start and end date forward allowing the user to use the same weekly historical sales as the system moves forward in time.

Measure Label	Description
Store Global Default Rounding Method	The Rounding Method is used when pack rounding the ideal receipt quantity (IRQ). The user selects the Rounding Method value from the following Picklist options: ▪ Unspecified ▪ Order Pack ▪ Normal 'Unspecified' indicates no value has been entered for the Rounding Method. The users may also select 'Unspecified' to remove the current value. Unspecified' defaults to 'Normal'.
Store Global Default Rounding Threshold	The Rounding Threshold represents the portion of a pack above which the replenishment plan is rounded up and below which it is rounded down. A zero threshold will always round up, and a threshold of 1 will always round down. If no value is entered, rounding threshold defaults to 1. Valid values are 0 through 1. Example: If an SRP user wants to round an order up to a pack if the demand is greater than 25 percent of a pack, the user would enter .25 in Rounding Threshold.
Store Global Default Safety Stock Level Factor	The Safety Stock Level Factor represents the amount of additional safety stock to carry in anticipation of unpredictable events (for instance, weather changes) or to provide additional safety stock during a special promotion or event. This will provide a temporary lift in the Receipt Point (RP) and Receive Up To Level (RUTL) values. The Safety Stock Level Factor is used in Time Supply, Hybrid, Poisson, Dynamic and Loaded SS Dynamic Replenishment Methods. Example: To increase safety stock by 25units, the user would enter a Safety Stock Level Factor of 25. Negative values may also be entered to decrease the safety stock level.
Store Global Default Service Level	The Service Level is used in the safety stock calculations for the Dynamic and Poisson replenishment methods. It is defined as the percentage of demand that the stock should be able to meet demand. Valid values are 0 through 1. Example: If an SRP user wants to carry enough safety stock to maintain a 90% customer service level, the user would enter .90 in Service Level.
Store Global Default Shelf Capacity	Shelf capacity is the amount of stock to fill a shelf to the desired maximum level. If the Shelf Capacity Flag is set to 'Yes', the shelf capacity is used to cap the receipt point and receive up to level. Any positive number, including zero, is valid.

Measure Label	Description
Store Global Default Shelf Capacity Flag	The Shelf Capacity Flag is used to determine if the receipt point and receive up to level should be capped by the shelf capacity. The user selects the Shelf Capacity Flag value from the following picklist options: ▪ Yes ▪ No ▪ Default Example: Selecting 'Yes' will cause SRP to use shelf capacity to cap receipt point and receive up to level. Selecting 'No' or 'Default' indicates SRP will not use shelf capacity to cap receipt point and receive up to level. 'Default' indicates no value has been entered for the Shelf Capacity Flag. The user may also select Default to remove the current value assigned.
Store Global Default Start Date Range	The Start Date Range parameter allows SRP users to select the date that should be used as the starting point for determining the historical sales data used by the "Sales Date Range" and "Factor AWS" replenishment methods. A pop-up calendar can be used to select the desired start date. Select a date less than or equal to the current date.
Store Global Default Time Supply Horizon	The Time Supply Horizon parameter is used to specify days of forecast in order to calculate a rate of sale. If a time supply horizon is specified, the rate of sale is used instead of the actual forecast when calculating demand over the time supply days for inventory target level calculations for the Time Supply Replenishment Method. Any positive integer, including zero, is valid. Example: To calculate a Rate of Sale (ROS) over a one week period, enter a value of 7 in Time Supply Horizon. The (ROS) is then calculated by summing the forecasted sales over the 7 days and dividing that number by 7.
Store Global Default Weekly Sales Max	Maximum stock boundary for the Factor AWS, Sales Date Range, and Loaded SS Dynamic replenishment methods. Any positive number, including zero, is valid
Store Global Default Weekly Sales Min	Minimum stock boundary for the Factor AWS, Sales Date Range, and Loaded SS Dynamic replenishment methods. Any positive number, including zero, is valid.
User Specified Store Global Default Presentation Stock	User Specified Store Global Default Presentation Stock is the minimum amount of stock in units desired to have on hand for display/sales purposes. User Specified Store Global Default Presentation Stock may be taken into consideration when calculating the Receipt Point and Receive up to Level, depending on the Boundary Stock selected. Any positive number, including zero, is valid.

Hidden Worksheet Measures

The following measures are hidden when using the default template. They can be displayed and maintained by using the Insert measure function of RPAS. Hidden measures may also be added to a template during configuration.

Measure Label	Description
Store Global Default Acceptable Loss	Acceptable Loss represents the percentage of a case that is acceptable to lose from spoilage in order to prevent stock outs. While Acceptable Loss is the value maintained in the database, SRP users can change either Acceptable Loss or Spoilage Threshold. If a user edits Acceptable Loss, Spoilage Threshold will be disabled for update and Spoilage Threshold is calculated as 1 minus Acceptable Loss. Valid values are 0 through 1. Example: If an SRP user finds it acceptable to lose 10% from spoilage, the user would enter .10 in Acceptable Loss.
Store Global Default Freshness Flag	The Freshness Flag is only used when the Inventory Aging Limit is set (indicating the SKU has a product life). When the Freshness Flag is "TRUE", SRP will ensure that a store replenishment plan is generated for at least the customer orders over Review Time (CORT) regardless of the inventory position. When the Freshness Flag is "TRUE", Maximum Selling Quantity (MSQ) is limited by product life.
Store Global Default Minimum Presentation Stock	The Store Global Default Minimum Presentation Stock indicates the minimum presentation quantity to be used in the calculation of store presentation stock. Any value greater than or equal to zero (0) is acceptable.
Store Global Default Presentation Stock Override Flag	The Store Global Default Presentation Stock Override Flag is used when calculating the Store Presentation Stock to indicate whether the override quantity should be used. When the Store Global Default Presentation Stock Override Flag is turned on ("TRUE"), the override quantity should be used.
Store Global Default Presentation Stock Override Quantity	The Store Global Default Presentation Stock Override Quantity is the value used when calculating Store Presentation Stock if the override flag is turned on ("TRUE").
Store Global Default Spoilage Threshold	Spoilage threshold is used as a pack rounding constraint. While Acceptable Loss is the value maintained in the database, SRP users can change either Acceptable Loss or Spoilage Threshold. If a user edits Default Spoilage Threshold, Acceptable Loss will be disabled for update and Acceptable Loss is calculated as 1 minus Spoilage Threshold. Valid values are 0 through 1. Example: If an SRP user wants to round a pack up if the spoilage threshold is greater than 90%, the user would enter .9 in Spoilage Threshold.

Measure Label	Description
Store Global Default Supplier Compliance Safety Stock	The Supplier Compliance Safety Stock parameter represents a 'number of days of supply' additional safety stock to deal with supplier and supply chain compliance issues. The days covered begins with the latest of Review Time or Inventory Selling Days. The calculated Supplier Compliance Safety Stock Units is added on to the Safety Stock. Any positive number, including zero, is valid. Example: To add an addition 7 days of supply, 7 would be entered in Supplier Compliance Safety Stock.
Store Global Default Weekly Base Sales Forecast %	The Store Global Default Weekly Base Sales Forecast % indicates what percentage of the Weekly Base Sales Forecast should be used in the calculation of store presentation stock. Values between 0 and 1 (inclusive) are valid. Zero ("0") indicates that 0% of the forecast should be used and "1" will indicate that 100% of the forecast should be used.

SRP Default Parameters (Sub-Class/Store Format) Tab

SRP Default Parameters (Sub-Class/Store Format) Worksheet

The SRP Default Parameters (Sub-Class/Store Format) Worksheet contains the default values at Sub-Class/Store Format for parameters that are used in generating and processing store replenishment plans.

Product	Location
DISPLAY CALCULATORS Downtown [List] [Left] [Right] [Double Right]	
Store Default AWS Factor	
Store Default Boundary Stock	
Store Default Demo Stock	
Store Default End Date Range	
Store Default Increment Percent	
Store Default Inventory Selling Days	
Store Default Max Safety Stock Days	
Store Default Max Safety Stock Units	
Store Default Max Stock	
Store Default Max Time Supply Days	
Store Default Min Safety Stock Days	
Store Default Min Safety Stock Units	
Store Default Min Stock	
Store Default Min Time Supply Days	
Store Default MSQ Constraint Indicator	
Store Default Percent of Pallet	
Store Default Promotion Presentation Stock Override Flag	
Store Default Repl Method	
Store Default Roll Weeks	
Store Default Rounding Method	
Store Default Rounding Threshold	
Store Default Safety Stock Level Factor	
Store Default Service Level	
Store Default Shelf Capacity	
Store Default Shelf Capacity Flag	
Store Default Start Date Range	
Store Default Time Supply Horizon	
Store Default Weekly Sales Max	
Store Default Weekly Sales Min	
User Specified Store Default Presentation Stock	
Measure	[Right]

SRP Default Parameters (Sub-class/Store Format) Worksheet

The SRP Default Parameters (Sub-Class/Store Format) Worksheet contains writeable measures at Sub-Class/Store Format level.

The following measures are displayed automatically when using the default template.

Measure Label	Description
Store Default AWS Factor	The AWS Factor allows SRP users to provide a numeric factor to be multiplied against the average weekly sales (AWS) to determine replenishment boundaries (safety stock, receipt point and receive up to level) for the Factor AWS replenishment method. Any positive number is valid. Example: To calculate a safety stock that is 50% of the average weekly sales, the user would enter an AWS Factor of .5.
Store Default Boundary Stock	The Boundary Stock identifier allows SRP users to select the stock level to use in calculating the Store Receipt Point and Store Receive Up to Level. This stock level is a combination of Safety Stock, Presentation Stock and/or Promotional Presentation Stock based on the identifiers listed below. If the identifier contains "vs", the greater value will be used. This parameter affects all replenishment methods. The user selects the boundary stock identifier from the following picklist options: ▪ SS vs PS + PPS ▪ SS vs PS ▪ SS vs PPS ▪ SS + PS + PPS ▪ SS + PS ▪ SS + PPS ▪ SS Where, SS = Safety Stock PS = Presentation Stock PPS = Promotional Presentation Stock The picklist default is SS vs PS + PPS. Example: Selecting SS vs PS will add the greater of SS or PS to the calculated Store Receipt Point and Store Receive Up to Level values.
Store Default Demo Stock	Amount of stock that is used as demonstration product, but is still available to sell. Demo Stock is added to the RP and RUTL levels for each day.
Store Default End Date Range	The End Date Range parameter allows SRP users to select the date that should be used as the ending point for determining the historical sales data used by the "Sales Date Range" and "Factor AWS" replenishment methods. A pop-up calendar can be used to select the desired end date. Select a date less than or equal to the current date.
Store Default Increment Percent	The Increment Percent acts as a multiplier for minimum and maximum stock that is designed to handle temporary fluctuation in demand for items using Min/Max Replenishment Method. An increment percentage factor can be used to temporarily increase or decrease targeted stocking levels without altering the established MIN and MAX values. Any positive number, including zero, is valid. Example: To use 120% of the Min and Max Stock, the user would enter an Increment Percent of 1.2.

Measure Label	Description
Store Default Inventory Selling Days	The Inventory Selling Days parameter is used to specify the number of days of forecast quantity to be used when calculating the Receive up to Level (RUTL) with the Hybrid, Dynamic, Poisson and Loaded SS Dynamic Replenishment Methods. The RUTL calculation will use the forecast demand over the greater of Inventory Selling Days and Review Time. Inventory Selling Days can be used to avoid producing very small frequent orders. Any positive integer, including zero, is valid. Example: To ensure an order will contain at least 14 days of supply, 14 would be entered as the number of Inventory Selling Days.
Store Default Max Safety Stock Days	The Max Safety Stock Days parameter is used to specify the maximum number of days of cover to be kept on hand as safety stock. If the user enters both Max Safety Stock Days and Max Safety Stock Units, the maximum safety stock boundary will use the larger of demand over max safety stock days and max safety stock units. Any positive integer, including zero, is valid. Example: To ensure the maximum safety stock will contain at least 14 days of supply, 14 would be entered in Max Safety Stock Days. If Max Safety Stock Units is greater than 14 days of supply, max units would be used as the maximum safety stock, otherwise maximum safety stock would be the number of units required to cover 14 days of demand, calculated as the sum of demand over the next 14 days beginning with the current day.
Store Default Max Safety Stock Units	The Max Safety Stock Units parameter is used to specify the maximum amount of inventory to be kept on hand as safety stock. If the user enters both Max Safety Stock Days and Max Safety Stock Units, the maximum safety stock boundary will use the larger of demand over max safety stock days and max safety stock units. Any positive number, including zero, is valid. Example: To ensure the maximum safety stock will contain at least 14 days of supply, 14 would be entered in Max Safety Stock Days. If Max Safety Stock Units is greater than 14 days of supply, max units would be used as the maximum safety stock, otherwise maximum safety stock would be the number of units required to cover 14 days of demand.
Store Default Max Stock	Max Stock is only used in the Min/Max Replenishment Method. It represents the maximum stock level in units that are desired on hand to satisfy demand. The receipt plan quantity is calculated to bring Net Inventory up to MAX. Any positive number, including zero, is valid.
Store Default Max Time Supply Days	Max Time Supply Days is only used in the Time Supply Replenishment Method. It represents maximum stock level in terms of number of days cover that that are desired on hand to satisfy demand. The receipt plan quantity is calculated to bring Net Inventory up to Maximum Time Supply Days of cover. Any positive integer, including zero, is valid. Example: To ensure an order will bring the inventory level up to 14 days of supply, 14 would be entered in Max Time Supply Days.

Measure Label	Description
Store Default Min Safety Stock Days	The Min Safety Stock Days parameter is used to specify the minimum number of days of cover to be kept on hand as safety stock. If the user enters both Min Safety Stock Days and Min Safety Stock Units, the minimum safety stock boundary will use the larger of demand over min safety stock days and min safety stock units. Any positive integer, including zero, is valid. Example: To ensure the minimum safety stock will contain at least 7 days of supply, 7 would be entered in Min Safety Stock Days. If Min Safety Stock Units is greater than 7 days of supply, min units would be used as the minimum safety stock, otherwise minimum safety stock would be the number of units required to cover 7 days of demand, calculated as the sum of demand over the next 7 days beginning with the current day.
Store Default Min Safety Stock Units	The Min Safety Stock Units parameter is used to specify the minimum amount of inventory to be kept on hand as safety stock. If the user enters both Min Safety Stock Days and Min Safety Stock Units, the minimum safety stock boundary will use the larger of demand over min safety stock days and min safety stock units. Any positive number, including zero, is valid. Example: To ensure the minimum safety stock will contain at least 7 days of supply, 7 would be entered in Min Safety Stock Days. If Min Safety Stock Units is greater than 7 days of supply, min units would be used as the minimum safety stock, otherwise minimum safety stock would be the number of units required to cover 7 days of demand.
Store Default Min Stock	Min Stock is only used in the Min/Max Replenishment Method. It represents the minimum stock level in units that are desired on hand to satisfy demand. Min Stock is used in determining the inventory level at which a replenishment is triggered. Any positive number, including zero, is valid.
Store Default Min Time Supply Days	Min Time Supply Days is only used in the Time Supply and Hybrid Replenishment Methods. It represents minimum stock level in terms of number of days cover that that are desired on hand to satisfy demand. Min Time Supply Days of cover is used in both safety stock and receipt point calculations. Any positive integer, including zero, is valid. Example: To ensure a minimum inventory level that will cover 7 days of supply, 7 would be entered in Min Time Supply Days.
Store Default MSQ Constraint Indicator	The Store Default MSQ Constraint Indicator indicates when the MSQ should be applied as a constraint during ordering decisions. If unspecified, the indicator is considered to be 'On' and MSQ will be used as a constraint.

Measure Label	Description
Store Default Percent of Pallet	Percent of pallet is used to determine if the Ideal Receipt Quantity for replenishment should be rounded to a full pallet. It represents the percentage threshold that case demand must exceed in order for pallet rounding to occur. Valid values are 0 through 1. While zero is a valid value, it indicates that the ideal receipt quantity will not be rounded by pallet. Example: If an SRP user wants to round an order up to a pallet if the case demand is greater than 75 percent of a pallet, the user would enter .75 in Percent of Pallet.
Store Default Promotion Presentation Stock Override Flag	The Store Default Promotion Presentation Stock Override Flag indicates what value should be used for Store Promotion Presentation Stock. When the override flag is turned on ("TRUE"), the Store Promotion Presentation Stock equals zero ("0").
Store Default Repl Method	The choice of Replenishment Method determines the type of calculations that will be used in generating a store replenishment method. The user selects the Replenishment Method from the following picklist options: ▪ Min/Max ▪ Time Supply ▪ Dynamic ▪ Hybrid ▪ No Replenishment ▪ Poisson Replenishment ▪ Loaded SS Dynamic ▪ Sales Week Range ▪ Factor AWS The picklist default is No Replenishment.
Store Default Roll Weeks	The Roll Weeks parameter indicates whether SRP logic should automatically roll the start and end date range settings forward one week or not. Roll weeks is used in the Factor AWS Sales Date Range Replenishment Methods. The user selects the Roll Weeks value from the following picklist options: ▪ Yes ▪ No ▪ Default Example: Selecting 'Yes' will cause the start and end date to roll forward one week, allowing the user to keep the weekly historical sales at the same relative distance in the past. Selecting 'No' will not move the start and end date forward allowing the user to use the same weekly historical sales as the system moves forward in time.

Measure Label	Description
Store Default Rounding Method	The Rounding Method is used when pack rounding the ideal receipt quantity (IRQ). The user selects the Rounding Method value from the following picklist options: ▪ Unspecified ▪ Order Pack ▪ Normal 'Unspecified' indicates no value has been entered for the Rounding Method. The users may also select 'Unspecified' to remove the current value. 'Unspecified' defaults to 'Normal'.
Store Default Rounding Threshold	The Rounding Threshold represents the portion of a pack above which the replenishment plan is rounded up and below which it is rounded down. A zero threshold will always round up, and a threshold of 1 will always round down. If no value is entered, rounding threshold defaults to 1. Valid values are 0 through 1. Example: If an SRP user wants to round an order up to a pack if the demand is greater than 25 percent of a pack, the user would enter .25 in Rounding Threshold.
Store Default Safety Stock Level Factor	The Safety Stock Level Factor represents the amount of additional safety stock to carry in anticipation of unpredictable events (for instance, weather changes) or to provide additional safety stock during a special promotion or event. This will provide a temporary lift in the Receipt Point (RP) and Receive Up To Level (RUTL) values. The Safety Stock Level Factor is used in Time Supply, Hybrid, Poisson, Dynamic and Loaded SS Dynamic Replenishment Methods. Example: To increase safety stock by 25 units, the user would enter a Safety Stock Level Factor of 25. Negative values may also be entered to decrease the safety stock level.
Store Default Service Level	The Service Level is used in the safety stock calculations for the Dynamic and Poisson replenishment methods. It is defined as the percentage of demand that the stock should be able to meet demand. Valid values are 0 through 1. Example: If an SRP user wants to carry enough safety stock to maintain a 90% customer service level, the user would enter .90 in Service Level.
Store Default Shelf Capacity	Shelf capacity is the amount of stock to fill a shelf to the desired maximum level. If the Shelf Capacity Flag is set to 'Yes', the shelf capacity is used to cap the receipt point and receive up to level. Any positive number, including zero, is valid.

Measure Label	Description
Store Default Shelf Capacity Flag	The Shelf Capacity Flag is used to determine if the receipt point and receive up to level should be capped by the shelf capacity. The user selects the Shelf Capacity Flag value from the following picklist options: ▪ Yes ▪ No ▪ Default Example: Selecting 'Yes' will cause SRP to use shelf capacity to cap receipt point and receive up to level. Selecting 'No' or 'Default' indicates SRP will not use shelf capacity to cap receipt point and receive up to level. 'Default' indicates no value has been entered for the Default Shelf Capacity Flag. The users may also select 'Default' to remove the current value.
Store Default Start Date Range	The Start Date Range parameter allows SRP users to select the date that should be used as the starting point for determining the historical sales data used by the "Sales Date Range" and "Factor AWS" replenishment methods. A pop-up calendar can be used to select the desired start date. Select a date less than or equal to the current date.
Store Default Time Supply Horizon	The Time Supply Horizon parameter is used to specify days of forecast in order to calculate a rate of sale. If a time supply horizon is specified, the rate of sale is used instead of the actual forecast when calculating demand over the time supply days for inventory target level calculations for the Time Supply Replenishment Method. Any positive integer, including zero, is valid. Example: To calculate a Rate of Sale (ROS) over a one week period, enter a value of 7 in Time Supply Horizon. The (ROS) is then calculated by summing the forecasted sales over the 7 days and dividing that number by 7.
Store Default Weekly Sales Max	Maximum stock boundary for the Factor AWS, Sales Date Range, and Loaded SS Dynamic replenishment methods. Any positive number, including zero, is valid
Store Default Weekly Sales Min	Minimum stock boundary for the Factor AWS, Sales Date Range, and Loaded SS Dynamic replenishment methods. Any positive number, including zero, is valid.
User Specified Store Default Presentation Stock	User Specified Store Global Default Presentation Stock is the minimum amount of stock in units desired to have on hand for display/sales purposes. User Specified Store Global Default Presentation Stock may be taken into consideration when calculating the Receipt Point and Receive up to Level, depending on the Boundary Stock selected. Any positive number, including zero, is valid.

Hidden Worksheet Measures

The following measures are hidden when using the default template. They can be displayed and maintained by using the Insert measure function of RPAS. Hidden measures may also be added to a template during configuration.

Measure Label	Description
Store Default Acceptable Loss	Acceptable Loss represents the percentage of a case that is acceptable to lose from spoilage in order to prevent stock outs. While Acceptable Loss is the value maintained in the database, SRP users can change either Acceptable Loss or Spoilage Threshold. If a user edits Acceptable Loss, Spoilage Threshold will be disabled for update and Spoilage Threshold is calculated as 1 minus Acceptable Loss. Valid values are 0 through 1. Example: If an SRP user finds it acceptable to lose 10% from spoilage, the user would enter .10 in Acceptable Loss.
Store Default Freshness Flag	The Freshness Flag is only used when the Inventory Aging Limit is set (indicating the SKU has a product life). When the Freshness Flag is "TRUE", SRP will ensure that a store replenishment plan is generated for at least the customer orders over Review Time (CORT) regardless of the inventory position. When the Freshness Flag is "TRUE", Maximum Selling Quantity (MSQ) is limited by product life.
Store Default Minimum Presentation Stock	The Store Default Minimum Presentation Stock indicates the minimum presentation quantity to be used in the calculation of store presentation stock. Any value greater than or equal to zero ("0") is acceptable.
Store Default Presentation Stock Override Flag	The Store Default Presentation Stock Override Flag is used when calculating the Store Presentation Stock to indicate whether the override quantity should be used. When the Store Default Presentation Stock Override Flag is turned on ("TRUE"), the override quantity should be used.
Store Default Presentation Stock Override Quantity	The Store Default Presentation Stock Override Quantity is the value used when calculating Store Presentation Stock if the override flag is turned on ("TRUE").
Store Default Spoilage Threshold	Spoilage threshold is used as a pack rounding constraint. While Acceptable Loss is the value maintained in the database, SRP users can change either Acceptable Loss or Spoilage Threshold. If a user edits Default Spoilage Threshold, Acceptable Loss will be disabled for update and Acceptable Loss is calculated as 1 minus Spoilage Threshold. Valid values are 0 through 1. Example: If an SRP user wants to round a pack up if the spoilage threshold is greater than 90%, the user would enter .9 in Spoilage Threshold.

Measure Label	Description
Store Default Supplier Compliance Safety Stock	The Supplier Compliance Safety Stock parameter represents a 'number of days of supply' additional safety stock to deal with supplier and supply chain compliance issues. The days covered begins with the latest of Review Time or Inventory Selling Days. The calculated Supplier Compliance Safety Stock Units is added on to the Safety Stock. Any positive number, including zero, is valid. Example: To add an addition 7 days of supply, 7 would be entered in Supplier Compliance Safety Stock.
Store Default Weekly Base Sales Forecast %	The Store Default Weekly Base Sales Forecast indicates what percentage of the Weekly Base Sales Forecast should be used in the calculation of store presentation stock. Values between 0 and 1 (inclusive) are valid. Zero ("0") indicates that 0% of the forecast should be used and "1" indicates that 100% of the forecast should be used.

SRP Alert Maintenance Workbook


The SRP Alert Maintenance workbook is used to set up the global (Sub-Class/Company), default (SKU/Company), and exception (SKU/Store) values that are used to populate alert measures. Global measures are used when no default or exception value exists. The values set here define the thresholds and horizons used to generate alerts. This workbook contains worksheets that are grouped into five tabs with the associated worksheets:

- SRP Alert Global Default (Sub-Class/Company) tab
 - SRP Alert Global Default (Sub-Class/Company)
- SRP Alert Default (SKU/Company) tab
 - SRP Alert Default (SKU/Company)
- SRP Alert Exception (SKU/Store) tab
 - SRP Alert Exception (SKU/Store)
- Run Masks tab
 - Run Masks
- Alert Masks tab
 - Alert Masks

SRP Alert Maintenance Wizard

Available Sub-Classes


The dialog box for Available Sub-Classes displayed below will show a list of all Sub-Classes in the AIP domain. The user's previous selections are already selected. The user has the ability to re-select which Sub-Classes will be accessed in the workbook. The positions default to the Sub-Class level. Standard RPAS functionality is available for this particular wizard page.



SRP Alert Maintenance Wizard – Available Sub-Classes

Available Stores


The dialog box for Available Stores displayed below will show a list of all Stores in the AIP domain. The user's previous selections are already selected. The user has the ability to re-select which Stores will be accessed in the workbook. The positions default to the Store level. Standard RPAS functionality is available for this particular wizard page.



SRP Alert Maintenance Wizard – Available Stores

Available Days

The dialog box for Available Days displayed below will show a list of all Days in the AIP domain. The user's previous selections are already selected. The user has the ability to re-select which Days will be accessed in the workbook. The positions default to the Day level and the days must be consecutive. Standard RPAS functionality is available for this particular wizard page.



SRP Alert maintenance Wizard – Available Days

SRP Alert Global Default (Sub-Class/Company) Tab

SRP Alert Global Default (Sub-Class/Company) Worksheet

The SRP Alert Global Default (Sub-Class/Company) worksheet contains the global Sub-Class/Company level default values for parameters that are used in generating alerts.

SRP Alert Global Default (Sub-Class/Company) Worksheet

The SRP Alert Global Default (Sub-Class/Company) worksheet contains writeable measures at the Sub-Class/Company level.

The following measures are displayed automatically when using the default template.

Measure Label	Description
Day on Day OOS Def Alerting Stores Ratio	The Day on Day Alerting Stores Ratio defines the threshold for the ratio of ranged stores out of stock (OOS) on the same day in consecutive weeks to the total number of ranged stores. This parameter represents the percentage threshold that must be exceeded when considering the generation of a Day on Day Repeat Out of Stocks alert. Valid values are 0 through 1. Example: If an SRP user wants to generate an alert if more than half of the ranged stores are out of stock on the same day in consecutive weeks, the user would enter .5 in Day on Day OOS Alerting Stores Ratio.
Day on Day OOS Def Corp. Lost Sales Volume	The Day on Day OOS Corp. Lost Sales Volume defines the threshold for the sum of lost sales for this SKU across ranged stores. This parameter represents the lost sales volume in units that must be exceeded when considering the generation of a Day on Day Repeat Out of Stocks alert. Any positive number, including zero, is valid.

Measure Label	Description
Day on Day OOS Def Count Threshold	The Day on Day OOS Count Threshold defines the threshold for the number of days a product is out of stock at a store for that SKU/Store to be considered as an exception. This parameter represents the number of days a store must be out of stock on the same day in consecutive weeks that must be exceeded before the Day on Day Repeat Out of Stocks alert is triggered. Any positive integer, including zero, is valid. Example: If an SRP user wants to generate an alert if a SKU/Store is out of stock on the same day for the past three weeks, 21 would be entered as the Day on Day OOS Count Threshold.
Day on Day OOS Def Horizon	Day on Day OOS Horizon defines the number of days in history that are reviewed when considering the generation of a Day on Day Repeat Out of Stocks alert. Any positive integer, including zero, is valid. Example: To review three weeks of history, 21 would be entered as the Day on Day OOS Horizon.
Def Stock Cover Days Threshold	The Stock Cover Days Threshold defines the threshold in number of days of supply that must be exceeded when considering the generation of an Overstock alert. Any positive integer, including zero, is valid. Example: If an SRP user wants to generate an alert only if the existing inventory will cover demand for two weeks or more, 14 would be entered as the Stock Cover Days Threshold.
High Dissipation Yesterday Def % of Sales	The High Dissipation Yesterday Def % of Sales defines the default threshold used in the High Dissipation Yesterday alert calculation; it represents a percentage of dissipation compared to sales. Zero is not a valid value. Valid percentages will be greater than 0.
High Dissipation Yesterday Def Alerting Stores Ratio	The High Dissipation Yesterday Def Alerting Stores Ratio defines the default threshold used in the High Dissipation Yesterday alert calculation; it represents a percentage of High Dissipation stores (that are not High Repeat Dissipation Stores) that exceed the High Dissipation % of sales ratio. Zero is not a valid value. Valid percentages will be greater than 0.
High Dissipation Yesterday Def Total % of Sales	The High Dissipation Yesterday Def Total % of Sales defines the default threshold used in the High Dissipation Yesterday alert calculation; it represents a percentage of total dissipation yesterday compared to total sales yesterday. Valid percentages will be greater than 0.
High Planned Orders Def Cases Over Weeks Demand	The High Planned Orders Cases Over Weeks Demand defines the volume threshold of demand forecast in cases over the next receipt period plus 7 days that planned orders must exceed when considering the generation of a High Planned Orders Alert. Any positive integer, including zero, is valid. Example: If an SRP user wants to be alerted when planned orders exceed the sum of forecasted demand for the next receipt period plus 7 days by 500 cases, 500 would be entered as the High Planned Orders Cases Over Weeks Demand.

Measure Label	Description
High Planned Orders Def Weeks Of Demand Multiple	The High Planned Orders Weeks Of Demand Multiple defines the factor by which demand forecasts over next receipt period plus 7 days is multiplied by when evaluating the High Planned Orders Alert. Any positive integer, including zero, is valid. Example: If an SRP user wants to be alerted when planned orders are double the sum of forecasted demand for the next receipt period plus 7 days, 2 would be entered as the High Planned Orders Weeks Of Demand Multiple.
High Proj Low Stock Def Alerting Stores Ratio	The High Proj Low Stock Alerting Stores Ratio defines the threshold for the ratio of ranged stores with projected low stock to the total number of ranged stores. This parameter represents the percentage threshold that must be exceeded when considering the generation of High Projected Low Stocks alert. Valid values are 0 through 1. Example: If an SRP user wants to generate an alert if more than half of the ranged stores have projected low stock, the user would enter .5 in High Proj Low Stock Alerting Stores Ratio.
High Proj Low Stock Def Low Level Percentage	The High Proj Low Stock Low Level Percentage defines the percentage below the Receive up to Level that Projected Inventory must be when considering the generation of High Projected Low Stocks alert. Valid values are 0 through 1. Example: If an SRP user wants to generate an alert if the Projected Inventory falls below 75% of the Receive up to Level, the user would enter .75 in High Proj Low Stock Low Level Percentage.
High Proj Low Stock Def Number of Low Stock Days	High Proj Low Stock Number of Low Stock Days defines the threshold for the number of days a product is projected low stock that must be exceeded before the High Projected Low Stocks alert is triggered. Any positive integer, including zero, is valid. Example: If an SRP user wants to generate an alert if a SKU/Store is projected low stock for 5 days, 5 would be entered as the High Proj Low Stock Number of Low Stock Days Threshold.
High Proj OOS / Low Stock Def Horizon	The High Proj OOS / Low Stock Horizon parameter defines the number of future days that are reviewed when considering the generation of a High Projected Low Stocks alert or a High Projected Out of Stock alert. Any positive integer, including zero, is valid. Example: To review two weeks in the future, 14 would be entered as the High Proj OOS / Low Stock Horizon.
High Proj OOS Def Alerting Stores Ratio	The High Proj OOS Alerting Stores Ratio defines the threshold for the ratio of ranged stores with projected out of stocks to the total number of ranged stores. This parameter represents the percentage threshold that must be exceeded when considering the generation of High Projected Out of Stock alert. Valid values are 0 through 1. Example: If an SRP user wants to generate an alert if more than half of the ranged stores have projected out of stocks, the user would enter .5 in High Proj OOS Alerting Stores Ratio.

Measure Label	Description
High Proj OOS Def Corp. Lost Sales % Forecast	The High Proj OOS Corp. Lost Sales % Forecast defines the threshold for the ratio of projected lost sales for all stores over the horizon to demand forecast for all stores over the horizon. This parameter represents the percentage threshold that must be exceeded when considering the generation of High Projected Out of Stock alert. Valid values are 0 through 1. Example: If an SRP user wants to generate an alert if the projected lost sales over the alert horizon are greater than 25% of the forecasted demand, the user would enter .25 in The High Proj OOS Corp. Lost Sales % Forecast.
High Proj OOS Def Corp. Lost Sales Volume over horizon	The High Proj OOS Corp. Lost Sales parameter defines the threshold for the sum of projected lost sales across for this SKU across ranged stores. This parameter represents the corporate lost sales volume threshold in units that must be exceeded when considering the generation of High Projected Out of Stock alert. Any positive integer, including zero, is valid.
High Proj OOS Def Number of Projected Days OOS	The High Proj OOS Number of Projected Days OOS parameter defines the threshold for the number of days this product is projected out of stock that must be exceeded before the High Projected Out of Stock alert is triggered. Any positive integer, including zero, is valid. Example: If an SRP user wants to generate an alert if a SKU/Store is projected out of stock for 3 days, 3 would be entered as the High Proj OOS Number of Projected Days OOS Threshold.
High Repeated Dissipation Def % of Sales	The High Repeated Dissipation Def % of Sales defines the default threshold used in the High Repeated Dissipation alert calculation; it represents a percentage of dissipation compared to sales. Zero is not a valid value. Valid percentages will be greater than 0.
High Repeated Dissipation Def Alerting Store Ratio	The High Repeated Dissipation Def Alerting Store Ratio defines the default threshold used in the High Repeated Dissipation alert calculation; it represents a percent of stores with high dissipation over a significant number of days. Valid percentages will be greater than 0.
High Repeated Dissipation Def Days	The High Repeated Dissipation Def Days defines the default threshold used in the High Repeated Dissipation alert calculation; it represents the number of days that must exceed the Dissipation % of Sales threshold. Zero is not a valid value. Valid values will be greater than 0.
High Repeated Dissipation Def Horizon	The High Repeated Dissipation Def Horizon defines the default Threshold used in the High Repeated Dissipation alert calculation; it represents the number of days to which the alert calculation will be limited. The Dissipation Days threshold must be exceeded within this horizon. Zero is not a valid value. Valid values will be greater than 0.

Measure Label	Description
Large Cons. OOS Def Alerting Stores Ratio	The Large Cons. OOS Alerting Stores Ratio defines the threshold for the ratio of ranged stores OOS on consecutive days to the total number of ranged stores. This parameter represents the percentage threshold that must be exceeded when considering the generation of the Large Consecutive Out of Stocks alert. Valid values are 0 through 1. Example: If an SRP user wants to generate an alert if more than 20% of the ranged stores were out of stock over the defined number of consecutive days, the user would enter .2 in Large Cons. OOS Alerting Stores Ratio.
Large Cons. OOS Def Corp. Lost Sales Volume over horizon	The Large Cons. OOS Corp. Lost Sales Volume over horizon defines the threshold for the sum of lost sales for this SKU across ranged stores. This parameter represents the lost sales volume in units that must be exceeded when considering the generation of a Large Consecutive Out of Stocks alert. Any positive number, including zero, is valid.
Large Cons. OOS Def Number of Consecutive Days OOS	The Large Cons. OOS Number of Consecutive Days OOS defines the threshold for the number of consecutive days a product is out of stock that must be exceeded before the Large Consecutive Out of Stocks alert is triggered. Any positive integer, including zero, is valid. Example: If an SRP user wants to generate an alert if a SKU/Store is out of stock for 4 consecutive days, 4 would be entered as the Large Cons. OOS Number of Consecutive Days OOS.
Large Non-Cons. OOS Def Alerting Stores Ratio	The Large Non-Cons. OOS Alerting Stores Ratio defines the threshold for the ratio of ranged stores OOS on non-consecutive days to the total number of ranged stores. This parameter represents the percentage threshold that must be exceeded when considering the generation of the Large Non-Consecutive Out of Stocks alert. Valid values are 0 through 1. Example: If an SRP user wants to generate an alert if more than 30% of the ranged stores were out of stock over the defined number of non-consecutive days, the user would enter .3 in Large Non-Cons. OOS Alerting Stores Ratio.
Large Non-Cons. OOS Def Corp. Lost Sales Volume over horizon	The Large Non-Cons. OOS Corp. Lost Sales Volume over horizon defines the threshold for the sum of lost sales for this SKU across ranged stores. This parameter represents the lost sales volume in units that must be exceeded when considering the generation of a Large Non-Consecutive Out of Stocks alert. Any positive number, including zero, is valid.
Large Non-Cons. OOS Def Number of Days OOS	The Large Non-Cons. OOS Number Days OOS defines the threshold for the number of non-consecutive days a product is out of stock that must be exceeded before the Large Non-Consecutive Out of Stocks alert is triggered. Any positive integer, including zero, is valid. Example: If an SRP user wants to generate an alert if a SKU/Store is out of stock for 5 non-consecutive days, 5 would be entered as the Large Non-Cons. OOS Number Days OOS.

Measure Label	Description
Large OOS Def Horizon	The Large OOS Horizon parameter defines the number of days in history that are reviewed when considering the generation of a Large Consecutive Out of Stocks alert or a Large Non-Consecutive Out of Stocks alert. Any positive integer, including zero, is valid. Example: To review two weeks of history, 14 would be entered as the Large OOS Horizon.
Large OOS Last Night Def Alerting Stores Ratio	The Large OOS Last Night Alerting Stores Ratio defines the threshold for the ratio of ranged stores OOS last night to the total number of ranged stores. This parameter represents the percentage threshold that must be exceeded when considering the generation of the Large Out of Stocks Last Night alert. Valid values are 0 through 1. Example: If an SRP user wants to generate an alert if more than 40% of the ranged stores were out of stock last night, the user would enter .4 in Large OOS Last Night Alerting Stores Ratio.
Large OOS Last Night Def Corp. Lost Sales % Possible Sales	The Large OOS Last Night Corp. Lost Sales % Possible Sales parameter defines the threshold for the ratio of lost sales last night to demand last night. Note this ratio compares all stores for a SKU, not just those that were out of stock last night. This parameter represents the percentage threshold that must be exceeded when considering the generation of the Large Out of Stocks Last Night alert. Valid values are 0 through 1. Example: If an SRP user wants to generate an alert if lost sales last night compared to possible sales last night (demand) were more than 20 %, the user would enter .2 in Large OOS Last Night Corp. Lost Sales % Possible Sales.
Large OOS Last Night Def Corp. Lost Sales Volume	The Large OOS Last Night Corp. Lost Sales Volume defines the threshold for the sum of lost sales last night for this SKU across ranged stores. This parameter represents the lost sales volume in units that must be exceeded when considering the generation of a Large Out of Stocks Last Night alert. Any positive number, including zero, is valid.
Overstock Def Units Threshold	The Overstock Units Threshold parameter defines the threshold in number of units which must be exceeded to trigger an Overstock Alert. Any positive integer, including zero, is valid.
Single Store Def Corp. Lost Sales Volume over Horizon	The Single Store Corp. Lost Sales Volume over Horizon defines the threshold for the sum of lost sales for this SKU at a single store. This parameter represents the lost sales volume in units that must be exceeded when considering the generation of a Single Store Availability Problems alert. Any positive number, including zero, is valid.
Single Store Def Horizon	The Single Store Horizon parameter defines the number of days in history that are reviewed when considering the generation of a Single Store Availability Problems. Any positive integer, including zero, is valid. Example: To review two weeks of history, 14 would be entered as the Single Store Horizon.

Measure Label	Description
Single Store Def Number of Days OOS	The Single Store Number of Days OOS defines the threshold for the number of days this product is out of stock for a store that must be exceeded to trigger a Single Store Availability Problems alert. Any positive integer, including zero, is valid. Example: If an SRP user wants to generate an alert if a product at a single store is out of stock for at least 4 days, 4 would be entered as the Single Store Number of Days OOS.

SRP Alert Default (SKU/Company) Tab

SRP Alert Default (SKU/Company) Worksheet

The SRP Alert Default (SKU/Company) Worksheet contains the default values at SKU/Company for parameters that are used in generating alerts.

Measure Label	Value
Day on Day OOS Alerting Stores Ratio	
Day on Day OOS Corp. Lost Sales Volume	
High Proj Low Stock Alerting Stores Ratio	
High Proj OOS Alerting Stores Ratio	
High Proj OOS Corp. Lost Sales % Forecast	
High Proj OOS Corp. Lost Sales Volume over horizon	
Large Cons. OOS Alerting Stores Ratio	0.50
Large Cons. OOS Corp. Lost Sales Volume over horizon	
Large Non-Cons. OOS Alerting Stores Ratio	
Large Non-Cons. OOS Corp. Lost Sales Volume over horizon	
Large OOS Last Night Alerting Stores Ratio	
Large OOS Last Night Corp. Lost Sales % Possible Sales	
Large OOS Last Night Corp. Lost Sales Volume	

SRP Alert Default (SKU/Company) Worksheet

The SRP Alert Global Default (SKU/Company) worksheet contains writeable measures at the SKU/Company level.

The following measures are displayed automatically when using the default template.

Measure Label	Description
Day on Day OOS Alerting Stores Ratio	The Day on Day Alerting Stores Ratio defines the threshold for the ratio of ranged stores out of stock (OOS) on the same day in consecutive weeks to the total number of ranged stores. This parameter represents the percentage threshold that must be exceeded when considering the generation of a Day on Day Repeat Out of Stocks alert. Valid values are 0 through 1. Example: If an SRP user wants to generate an alert if more than half of the ranged stores are out of stock on the same day in consecutive weeks, the user would enter .5 in Day on Day OOS Alerting Stores Ratio.

Measure Label	Description
Day on Day OOS Corp. Lost Sales Volume	The Day on Day OOS Corp. Lost Sales Volume defines the threshold for the sum of lost sales for this SKU across ranged stores. This parameter represents the lost sales volume in units that must be exceeded when considering the generation of a Day on Day Repeat Out of Stocks alert. Any positive number, including zero, is valid.
Day on Day OOS Day on Day Count Threshold	The Day on Day OOS Day on Day Count Threshold defines the threshold for the number of days a product is out of stock at a store for that SKU/Store to be considered as an exception. This parameter represents the number of days a store must be out of stock on the same day in consecutive weeks that must be exceeded before the Day on Day Repeat Out of Stocks alert is triggered. Any positive integer, including zero, is valid. Example: If an SRP user wants to generate an alert if a SKU/Store is out of stock on the same day for the past three weeks 3 would be entered as the Day on Day OOS Day on Day Count Threshold.
High Proj Low Stock Alerting Stores Ratio	The High Proj Low Stock Alerting Stores Ratio defines the threshold for the ratio of ranged stores with projected low stock to the total number of ranged stores. This parameter represents the percentage threshold that must be exceeded when considering the generation of High Projected Low Stocks alert. Valid values are 0 through 1. Example: If an SRP user wants to generate an alert if more than half of the ranged stores have projected low stock, the user would enter .5 in High Proj Low Stock Alerting Stores Ratio.
High Dissipation Yesterday % of Sales	The High Dissipation Yesterday % of Sales defines the threshold used in the High Dissipation Yesterday alert calculation; it represents a percentage of dissipation compared to sales. Zero is not a valid value. Valid percentages will be greater than 0.
High Dissipation Yesterday Alerting Stores Ratio	The High Dissipation Yesterday Alerting Stores Ratio defines the threshold used in the High Dissipation Yesterday alert calculation; it represents a percentage of High Dissipation stores (that are not High Repeat Dissipation Stores) that exceeded the High Dissipation % of sales ratio. Zero is not a valid value. Valid percentages will be greater than 0.
High Dissipation Yesterday Total % of Sales	The High Dissipation Yesterday Total % of Sales defines the threshold used in the High Dissipation Yesterday alert calculation; it represents a percentage of total dissipation yesterday compared to total sales yesterday. Valid percentages will be greater than 0.
High Proj OOS Alerting Stores Ratio	The High Proj OOS Alerting Stores Ratio defines the threshold for the ratio of ranged stores with projected out of stocks to the total number of ranged stores. This parameter represents the percentage threshold that must be exceeded when considering the generation of High Projected Out of Stock alert. Valid values are 0 through 1. Example: If an SRP user wants to generate an alert if more than half of the ranged stores have projected out of stocks, the user would enter .5 in High Proj OOS Alerting Stores Ratio.

Measure Label	Description
High Proj OOS Corp. Lost Sales % Forecast	The High Proj OOS Corp. Lost Sales % Forecast defines the threshold for the ratio of projected lost sales for all stores over the horizon to demand forecast for all stores over the horizon. This parameter represents the percentage threshold that must be exceeded when considering the generation of High Projected Out of Stock alert. Valid values are 0 through 1. Example: If an SRP user wants to generate an alert if the projected lost sales over the alert horizon are greater than 25% of the forecasted demand, the user would enter .25 in The High Proj OOS Corp. Lost Sales % Forecast.
High Proj OOS Corp. Lost Sales Volume over horizon	The High Proj OOS Corp. Lost Sales parameter defines the threshold for the sum of projected lost sales across for this SKU across ranged stores. This parameter represents the corporate lost sales volume threshold in units that must be exceeded when considering the generation of High Projected Out of Stock alert. Any positive integer, including zero, is valid.
Large Cons. OOS Alerting Stores Ratio	The Large Cons. OOS Alerting Stores Ratio defines the threshold for the ratio of ranged stores OOS on consecutive days to the total number of ranged stores. This parameter represents the percentage threshold that must be exceeded when considering the generation of the Large Consecutive Out of Stocks alert. Valid values are 0 through 1. Example: If an SRP user wants to generate an alert if more than 20% of the ranged stores were out of stock over the defined number of consecutive days, the user would enter .2 in Large Cons. OOS Alerting Stores Ratio.
Large Cons. OOS Corp. Lost Sales Volume over horizon	The Large Cons. OOS Corp. Lost Sales Volume over horizon defines the threshold for the sum of lost sales for this SKU across ranged stores. This parameter represents the lost sales volume in units that must be exceeded when considering the generation of a Large Consecutive Out of Stocks alert. Any positive number, including zero, is valid.
Large Non-Cons. OOS Alerting Stores Ratio	The Large Non-Cons. OOS Alerting Stores Ratio defines the threshold for the ratio of ranged stores OOS on non-consecutive days to the total number of ranged stores. This parameter represents the percentage threshold that must be exceeded when considering the generation of the Large Non-Consecutive Out of Stocks alert. Valid values are 0 through 1. Example: If an SRP user wants to generate an alert if more than 30% of the ranged stores were out of stock over the defined number of non-consecutive days, the user would enter .3 in Large Non-Cons. OOS Alerting Stores Ratio.
High Repeated Dissipation % of Sales	The High Repeated Dissipation % of Sales defines the threshold used in the High Repeated Dissipation alert calculation; it represents a percentage of dissipation compared to sales. Zero is not a valid value. Valid percentages will be greater than 0.

Measure Label	Description
High Repeated Dissipation Alerting Stores Ratio	The High Repeated Dissipation Alerting Stores Ratio defines the threshold used in the High Repeated Dissipation alert calculation; it represents a percent of stores with high dissipation over a significant number of days. Valid percentages will be greater than 0.
High Repeated Dissipation Days	The High Repeated Dissipation Days defines the threshold used in the High Repeated Dissipation alert calculation; it represents the number of days that must exceed the Dissipation % of Sales threshold. Zero is not a valid value. Valid values will be greater than 0.
High Repeated Dissipation Horizon	The High Repeated Dissipation Horizon defines the threshold used in the High Repeated Dissipation alert calculation; it represents the number of days to which the alert calculation will be limited. The Dissipation Days threshold must be exceeded within this horizon. Zero is not a valid value. Valid values will be greater than 0.
Large Non-Cons. OOS Corp. Lost Sales Volume over horizon	The Large Non-Cons. OOS Corp. Lost Sales Volume over horizon defines the threshold for the sum of lost sales for this SKU across ranged stores. This parameter represents the lost sales volume in units that must be exceeded when considering the generation of a Large Non-Consecutive Out of Stocks alert. Any positive number, including zero, is valid.
Large OOS Last Night Alerting Stores Ratio	The Large OOS Last Night Alerting Stores Ratio defines the threshold for the ratio of ranged stores OOS last night to the total number of ranged stores. This parameter represents the percentage threshold that must be exceeded when considering the generation of the Large Out of Stocks Last Night alert. Valid values are 0 through 1. Example: If an SRP user wants to generate an alert if more than 40% of the ranged stores were out of stock last night, the user would enter .4 in Large OOS Last Night Alerting Stores Ratio.
Large OOS Last Night Corp. Lost Sales % Possible Sales	The Large OOS Last Night Corp. Lost Sales % Possible Sales parameter defines the threshold for the ratio of lost sales last night to demand last night. Note this ratio compares all stores for a SKU, not just those that were out of stock last night. This parameter represents the percentage threshold that must be exceeded when considering the generation of the Large Out of Stocks Last Night alert. Valid values are 0 through 1. Example: If an SRP user wants to generate an alert if lost sales last night compared to possible sales last night (demand) were more than 20 %, the user would enter .2 in Large OOS Last Night Corp. Lost Sales % Possible Sales.
Large OOS Last Night Corp. Lost Sales Volume	The Large OOS Last Night Corp. Lost Sales Volume defines the threshold for the sum of lost sales last night for this SKU across ranged stores. This parameter represents the lost sales volume in units that must be exceeded when considering the generation of a Large Out of Stocks Last Night alert. Any positive number, including zero, is valid.

SRP Alert Exception (SKU/Store) Tab

SRP Alert Exception (SKU/Store) Worksheet

The SRP Alert Exception (SKU/Store) worksheet contains the SKU/Store exception level values for parameters that are used in generating alerts.

Measure Label	Description
Day on Day OOS Count Threshold	The Day on Day OOS Count Threshold defines the threshold for the number of days a product is out of stock at a store for that SKU/Store to be considered as an exception. This parameter represents the number of days a store must be out of stock on the same day in consecutive weeks that must be exceeded before the Day on Day Repeat Out of Stocks alert is triggered. Any positive integer, including zero, is valid. Example: If an SRP user wants to generate an alert if a SKU/Store is out of stock on the same day for the past three weeks, 21 would be entered as the Day on Day OOS Count Threshold.
Day on Day OOS Horizon	Day on Day OOS Horizon defines the number of days in history that are reviewed when considering the generation of a Day on Day Repeat Out of Stocks alert. Any positive integer, including zero, is valid. Example: To review three weeks of history, 21 would be entered as the Day on Day OOS Horizon.

SRP Alert Exception (SKU/Store) Worksheet

The SRP Alert Exception (SKU/Store) worksheet contains writeable measures at the SKU/Store level.

The following measures are displayed automatically when using the default template.

Measure Label	Description
Day on Day OOS Count Threshold	The Day on Day OOS Count Threshold defines the threshold for the number of days a product is out of stock at a store for that SKU/Store to be considered as an exception. This parameter represents the number of days a store must be out of stock on the same day in consecutive weeks that must be exceeded before the Day on Day Repeat Out of Stocks alert is triggered. Any positive integer, including zero, is valid. Example: If an SRP user wants to generate an alert if a SKU/Store is out of stock on the same day for the past three weeks, 21 would be entered as the Day on Day OOS Count Threshold.
Day on Day OOS Horizon	Day on Day OOS Horizon defines the number of days in history that are reviewed when considering the generation of a Day on Day Repeat Out of Stocks alert. Any positive integer, including zero, is valid. Example: To review three weeks of history, 21 would be entered as the Day on Day OOS Horizon.

Measure Label	Description
High Planned Orders Cases Over Weeks Demand	The High Planned Orders Cases Over Weeks Demand defines the volume threshold of demand forecast in cases over the next receipt period plus 7 days that planned orders must exceed when considering the generation of a High Planned Orders Alert. Any positive integer, including zero, is valid. Example: If an SRP user wants to be alerted when planned orders exceed the sum of forecasted demand for the next receipt period plus 7 days by 500 cases, 500 would be entered as the High Planned Orders Cases Over Weeks Demand.
High Planned Orders Weeks Of Demand Multiple	The High Planned Orders Weeks Of Demand Multiple defines the factor by which demand forecasts over next receipt period plus 7 days is multiplied by when evaluating the High Planned Orders Alert. Any positive integer, including zero, is valid. Example: If an SRP user wants to be alerted when planned orders are double the sum of forecasted demand for the next receipt period plus 7 days, 2 would be entered as the High Planned Orders Weeks Of Demand Multiple.
High Proj Low Stock Number of Low Stock Days	High Proj Low Stock Number of Low Stock Days defines the threshold for the number of days a product is projected low stock that must be exceeded before the High Projected Low Stocks alert is triggered. Any positive integer, including zero, is valid. Example: If an SRP user wants to generate an alert if a SKU/Store is projected low stock for 5 days, 5 would be entered as the High Proj Low Stock Number of Low Stock Days Threshold.
High Proj OOS / Low Stock Horizon	The High Proj OOS / Low Stock Horizon parameter defines the number of future days that are reviewed when considering the generation of a High Projected Low Stocks alert or a High Projected Out of Stock alert. Any positive integer, including zero, is valid. Example: To review two weeks in the future, 14 would be entered as the High Proj OOS / Low Stock Horizon.
High Proj Number of Projected Days OOS	The High Proj OOS Number of Projected Days OOS parameter defines the threshold for the number of days this product is projected out of stock that must be exceeded before the High Projected Out of Stock alert is triggered. Any positive integer, including zero, is valid. Example: If an SRP user wants to generate an alert if a SKU/Store is projected out of stock for 3 days, 3 would be entered as the High Proj OOS Number of Projected Days OOS Threshold.
Large Cons. OOS Number of Consecutive Days OOS	The Large Cons. OOS Number of Consecutive Days OOS defines the threshold for the number of consecutive days a product is out of stock that must be exceeded before the Large Consecutive Out of Stocks alert is triggered. Any positive integer, including zero, is valid. Example: If an SRP user wants to generate an alert if a SKU/Store is out of stock for 4 consecutive days, 4 would be entered as the Large Cons. OOS Number of Consecutive Days OOS.

Measure Label	Description
Large Non-Cons. OOS Number of Days OOS	The Large Non-Cons. OOS Number Days OOS defines the threshold for the number of non-consecutive days a product is out of stock that must be exceeded before the Large Non-Consecutive Out of Stocks alert is triggered. Any positive integer, including zero, is valid. Example: If an SRP user wants to generate an alert if a SKU/Store is out of stock for 5 non-consecutive days, 5 would be entered as the Large Non-Cons. OOS Number Days OOS.
Large OOS Horizon	The Large OOS Horizon parameter defines the number of days in history that are reviewed when considering the generation of a Large Consecutive Out of Stocks alert or a Large Non-Consecutive Out of Stocks alert. Any positive integer, including zero, is valid. Example: To review two weeks of history, 14 would be entered as the Large OOS Horizon.
Overstock Units Threshold	The Overstock Units Threshold parameter defines the threshold in number of units which must be exceeded to trigger an Overstock Alert. Any positive integer, including zero, is valid.
Single Store Corp. Lost Sales Volume over Horizon	The Single Store Corp. Lost Sales Volume over Horizon defines the threshold for the sum of lost sales for this SKU at a single store. This parameter represents the lost sales volume in units that must be exceeded when considering the generation of a Single Store Availability Problems alert. Any positive number, including zero, is valid.
Single Store Horizon	The Single Store Horizon parameter defines the number of days in history that are reviewed when considering the generation of a Single Store Availability Problems. Any positive integer, including zero, is valid. Example: To review two weeks of history, 14 would be entered as the Single Store Horizon.
Single Store Number of Days OOS	The Single Store Number of Days OOS defines the threshold for the number of days this product is out of stock for a store that must be exceeded to trigger a Single Store Availability Problems alert. Any positive integer, including zero, is valid. Example: If an SRP user wants to generate an alert if a product at a single store is out of stock for at least 4 days, 4 would be entered as the Single Store Number of Days OOS.
Stock Cover Days Threshold	The Stock Cover Days Threshold defines the threshold in number days of supply that must be exceeded when considering the generation of an Overstock alert. Any positive integer, including zero, is valid. Example: If an SRP user wants to generate an alert only if the existing inventory will cover demand for two weeks or more, 14 would be entered as the Stock Cover Days Threshold.

Run Masks Tab

Alert Day Masks (DOW) Worksheet

The Alert Days Masks worksheet contains masks for SRP alerts that allow the user to 'turn off' the alert, or keep SRP from generating that alert on a specific day of the week.

	Sunday	Monday	Tuesday
Day on Day Repeat Out of Stocks DOW Mask	☒	☒	☒
High Planned Orders DOW Mask	☐	☒	☐
High Projected Low Stocks DOW Mask	☒	☒	☒
High Projected Out of Stock DOW Mask	☒	☒	☒
Large Consecutive Out of Stocks DOW Mask	☒	☒	☒
Large Non-Consecutive Out of Stocks DOW Mask	☒	☒	☒
Large Out of Stocks Last Night DOW Mask	☒	☒	☒
No Like SKU Found DOW Mask	☐	☐	☐
RDF Detail Alert DOW Mask	☒	☐	☐
Single Store Availability Problems DOW Mask	☒	☒	☒
SRP Overstock DOW Mask	☒	☒	☒

Alert Day Masks (DOW) Worksheet

The Alert Day Masks worksheet contains the following writeable measures at the Day of Week (DOW) level. The SRP user can 'check' a box to stop that alert from being run on the day checked.

The following measures are displayed automatically when using the default template.

- Day on Day Repeat Out of Stock DOW Mask
- High Dissipation Yesterday Alert DOW Mask
- High Planned Orders DOW Mask
- High Projected Low Stocks DOW Mask
- High Projected Out of Stock DOW Mask
- High Repeated Dissipation Alert DOW Mask
- Large Consecutive Out of Stocks DOW Mask
- Large Non-Consecutive Out of Stocks DOW Mask
- Large Out of Stocks Last Night DOW Mask
- No Like SKU Found DOW Mask
- RDF Detail Alert DOW Mask
- Single Store Availability Problems DOW Mask
- SRP Over Stock DOW Mask

Alert Masks Tab

Alert Masks Worksheet

The Alert Masks Worksheet contains masks for SRP alerts that allow the user to 'turn off' the alert, or keep SRP from generating that alert.

Product	Location	Calendar		
100035008 - CALCULATOR.GRAPHING.SILVER	S1000000001 - Minn			
	04/01/06	04/02/06	04/03/06	04/04/06
Day on Day Repeat Out of Stocks Mask	☒	☒	☒	☒
High Planned Orders Mask	☒	☒	☐	☐
High Projected Low Stocks Mask	☒	☒	☒	☒
High Projected Out of Stock Mask	☒	☒	☒	☒
Large Consecutive Out of Stocks Mask	☒	☒	☒	☒
Large Non-Consecutive Out of Stocks Mask	☒	☒	☒	☒
Large Out of Stocks Last Night Mask	☒	☒	☒	☒
No Like SKU Found Mask	☒	☒	☒	☒
RDF Detail Alert Mask	☐	☐	☐	☒
Single Store Availability Problems Mask	☒	☒	☒	☒
SRP Overstock Mask	☒	☒	☒	☒

Alert Masks Worksheet

The SRP Alert Masks worksheet contains the following writeable measures at the SKU/Store/Day level. The SRP user can 'check' a box to stop that alert from being run. The following measures are displayed automatically when using the default template.

- Day on Day Repeat Out of Stock Mask
- High Dissipation Yesterday Mask
- High Planned Orders Mask
- High Projected Low Stocks Mask
- High Projected Out of Stock Mask
- High Repeated Dissipation Mask
- Large Consecutive Out of Stocks Mask
- Large Non-Consecutive Out of Stocks Mask
- Large Out of Stocks Last Night Mask
- No Like SKU Found Mask
- RDF Detail Alert Mask
- Single Store Availability Problems Mask
- SRP Over Stock Mask


SRP by Source Distribution Review Workbook

The SRP By Source Distribution Review workbook displays information regarding the distribution of goods and inventory volumes for a particular store that can be used to resolve alerts, modify replenishment parameters, manage business needs, and so on. The 'values' reflected in the worksheets are 'for review' use only.

SRP by Source Distribution Review Wizard

Available SKUs


The dialog box for Available SKUs displayed below will show a list of all SKUs in the AIP domain. The user's previous selections are already selected. The user has the ability to re-select which SKUs will be accessed in the workbook. Standard RPAS functionality is available for this particular wizard page.



SRP by Source Distribution Review Wizard – Available SKUs

Available Source Stocking Points

The dialog box for Available Source Stocking Points displayed below will show a list of all Source Stocking Points in the AIP domain that source the selected SKU(s). The user has the ability to select which Source Stocking Points will be accessed in the workbook. Standard RPAS functionality is available for this particular wizard page.




SRP by Source Distribution Review Wizard – Available Source Stocking Points

If there were no Source Stocking Points for the SKU(s) selected from the previous wizard screen, the user will be notified by the following warning message: "There is no Source Stocking Point for the SKU(s) selected."

Available Stores


The dialog box for Available Stores displayed below will show a list of all Stores in the AIP domain that are sourced by the selected Source Stocking Point(s). The user has the ability to select which Stores will be accessed in the workbook. Standard RPAS functionality is available for this particular wizard page.



SRP by Source Distribution Review Wizard – Available Stores

Available Days

The dialog box for Available Days displayed below will show a list of all dates in the AIP domain. No filtering is done based on the Store Source. The user has the ability to select which dates will be accessed in the workbook. If multiple days are selected, they all must be consecutive days and today must be included. Standard RPAS functionality is available for this particular wizard page.



SRP by Source Distribution Review Wizard – Available Days

Distribution Review Tab

Distribution Review Worksheet (SKU/Store/Day)

Product	Location	Calendar			
100035008 - CALCULATOR, GRAPHING, SILVER	S303 - MISH	04/01/06	04/02/06	04/03/06	04/04/06
Store Available to Plan Receipt		☐	☐	☒	☐
Store Commodity Prevent Release		0	0	0	0
Store Demand Forecast		100.00	100.00	75.00	50.00
Store Expected Receipts		0.00	0.00	0.00	0.00
Store In Transits		0.00	0.00	0.00	0.00
Store On Orders		0.00	0.00	0.00	0.00
Store Ordering Pack Size		1.00	1.00	1.00	1.00
Store Projected Inventory		0.00	0.00	0.00	325.00
Store Receipt Point		0.00	100.00	100.00	100.00
Store Receive Up to Level		0.00	400.00	400.00	400.00
Store Reconciled Orders		☐	☐	☐	☐
Store Reconciliation Adjustment		0.00	0.00	0.00	0.00
Store Release Schedule			1	1	1
Store Released CRP		0.00	0.00	400.00	0.00
Store Repl Method (expanded)		Min Max	Min Max	Min Max	Min Max

Distribution Review Worksheet (SKU/Store/Day)

The following measures appear in this worksheet. All measures are read-only for all users.

Measure Label	Description
Store Available To Plan Receipt	The Store Available To Plan Receipt (ATP) indicates the days on which a store may plan a receipt based on the store's release schedule. A checkmark in a box indicates a receipt may be planned on that day.
Store Commodity Prevent Release	Store Commodity Prevent Release indicates whether or not the release of store-level orders should be prevented based on the Store Prevent Release flag.
Store Demand Forecast	The Store Demand Forecast is the forecast of the store's future sales. Note: Demand Forecast is loaded from an external forecasting system.
Store Expected Receipts	Store Expected Receipts (ER) are orders that have already been executed and therefore need to be considered when planning future orders for a store. Store Expected Receipts is the sum of in-transits and on orders. Note: In-transits and on orders s are loaded to SRP from an external system.
Store Intransits	Store Intransits represents Inventory in transit from warehouses and suppliers to store. Note: This measure is loaded from an external system.

Measure Label	Description
Store On Orders	Store On Orders are fixed orders currently being processed for delivery to store either from warehouses or directly from suppliers Note: This measure is loaded from an external system.
Store Ordering Pack Size	The Store Ordering Pack Size represents the primary pack size to be used when ordering a SKU for a store (either from a warehouse or from a supplier). Note: Store Ordering Pack Size is loaded from Data Management online (DMo).
Store Projected Inventory	Store Projected Inventory (PI) is calculated in AIP batch and in the Interactive Evaluation workbook “What If” processing. It represents a projection of the opening inventory position for any day in the planning horizon at a specific store. None of that day’s activities (either receipts or demand) are reflected in PI, and so it is often referred to as a “beginning of day” position. PI on a given day is calculated as the PI of the previous day plus the net impact of all demand and replenishments on the previous day. Previous day demand is consists of forecasted demand plus any customer orders (CO) on that day. Previous day replenishments consist of Expected and Planned Receipts.
Store Receipt Point	The Store Receipt Point (RP) represents the inventory level below which an order should be triggered. Receipt point is calculated differently based on the selected Replenishment Method. Store Receipt Point is only calculated on Available to Plan receipt days.
Store Receive Up to Level	The Receive Up To level (RUTL) denotes the target level of inventory when generating an order. Receive Up To Level is calculated differently based on the selected Replenishment Method. Store Receive Up to Level is only calculated on Available to Plan receipt days.
Store Reconciled Orders	The Store Reconciled Orders is an indicator informing users which indicates which orders have been reconciled.
Store Reconciliation Adjustment	The Store Reconciliation Adjustment represents the difference between the Unconstrained Receipt Plan and the Store Receipt Plan due to inventory constraints, inventory availability at the source location.
Store Release Schedule	The Store Release Schedule represents the date an order must be released by to receive it by a certain date. The release schedule is calculated in Data Management (DM) based on lead time and order cycle.
Store Released CRP	Store Released CRP represents the constrained receipt plan quantity that was released to the warehouse or supplier.

Measure Label	Description
Store Repl Method (expanded)	The choice of Replenishment Method determines the calculations that will be used in generating a store replenishment method. The Replenishment Method options are: ▪ Min/Max ▪ Time Supply ▪ Dynamic ▪ Hybrid ▪ No Replenishment ▪ Poisson Replenishment ▪ Loaded SS Dynamic ▪ Sales Week Range ▪ Factor AWS The default is No Replenishment The expanded version of Store Repl Method will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered.
Store Safety Stock	Store Safety Stock (SS) is inventory held at a location to mitigate the risks of stock outs caused by variability in forecasted demand. Safety stock is calculated differently based on the selected Replenishment Method. All replenishment methods allow the safety stock to be bound by minimum and maximum values. Store Safety Stock is only calculated on Available to Plan receipt days.
Store Source Label	The Store Source Label identifies the source from which this store receives inventory.

SRP Evaluation Workbook

The SRP Evaluation workbook allows users to examine the store replenishment plan. This workbook is read only for all measures.

This workbook contains worksheets that are grouped into three tabs:


- SRP Replenishment Plan – This tab contains the following six worksheets that allow you to review replenishment plan information:
 - SRP Replenishment Summary (SKU/Store/Day)
 - SRP Replenishment Plan (SKU/Store/Week)
 - SRP Replenishment Plan (SKU/Store)
 - SRP Replenishment Plan Parameters (Store)
 - SRP Replenishment Plan Parameters (SKU)
 - WH Inventory Analysis (SKU Group/Warehouse/Day)
 - Company Level Introductory Analysis
- SRP Exception Summary – This tab contains the following three worksheets that allow you to examine alert summary data at the specified level:
 - SRP Exception Summary (Weather Region/SKU)
 - SRP Exception Summary (Corporate/SKU)
 - SRP Exception Summary (Store Format/SKU)
- SRP Overstock Alert Summary – This tab contains the following two worksheets that allow you to review details associated with an Overstock alert:
 - SRP Overstock Details (SKU/Store/Day)
 - SRP Overstock Alert (SKU)

SRP Evaluation Wizard

Build Workbook Using Ads?

This wizard will not be displayed if the “Store Ads” measure is not populated or if no ads exist for SKUs within the user’s security level.

If the Store Ads measure is populated, the user will first be asked, using radio buttons, whether or not to base the workbook selections on an ad. The wizard selection will default to “Do Not Use Ads”.



The image shows a Windows-style dialog box titled "SRP Evaluation Wizard". The dialog has a blue title bar with a close button (X) in the top right corner. The main area is light beige. The text "Build workbook using Ads?" is centered. Below it are two radio buttons: "Use Ads" (which is selected, indicated by a green dot) and "Do Not Use Ads" (which is unselected, indicated by a blue dot). At the bottom of the dialog, there are five buttons: "Cancel", "<Back", "Next>", "Finish", and "Help".


SRP Evaluation Wizard – Use Ads

If the selection is set to “Do Not Use Ads” once the user hits the Next button, the user will be able to select from the Available SKUs. Otherwise, the user will be able to select from Available Ads.

Available Ads

This wizard will not be displayed if “Do Not Use Ads” was selected.

The dialog box for Available Ads will show a list of all Ads for a SKU/Store combination in the AIP domain. Standard RPAS functionality is available for this particular wizard page.




SRP Evaluation Wizard – Available Ads

Note: Only one ad can be selected. If the user attempts to select more than one ad, he/she will see an error message stating “Only one ad may be selected.”

Available SKUs

This wizard will be displayed first if the 'Store Ads' measure is not populated. The dialog box for Available SKUs will show a list of all active SKUs in the AIP domain. A SKU is considered active if, for at least one SKU pack size at a particular destination, the lead time is ≥ 0 for any source on any day within the scheduled horizon.


Also, if the user didn't select any Ads, the dialog box for Available SKUs displayed below will show a list of all active SKUs in the AIP domain. Otherwise, the Available SKUs will be filtered based on the Ads selected. Standard RPAS functionality is available for this particular wizard page.



SRP Evaluation Wizard – Available SKUs

Available Stores


If the user didn't select any Ads, the dialog box for Available Stores displayed below will show a list of all Stores in the AIP domain. Otherwise, the Available Stores will be filtered based on the Ads and SKUs selected. Standard RPAS functionality is available for this particular wizard page.



SRP Evaluation Wizard – Available Stores

Available Days

The dialog box for Available Days displayed below will show a list of all Days in the AIP domain. If available, the user's previous selections are already selected. The user has the ability to re-select which dates will be accessed in the workbook. Please note if all days in the scheduled horizon are not selected, workbook calculations may display different values from batch. Standard RPAS functionality is available for this particular wizard page.



SRP Evaluation Wizard – Available Days

SRP Replenishment Plan Tab

SRP Replenishment Summary (SKU/Store/Day) Worksheet

	04/01/06	04/02/06	04/03/06	04/04/06
Store Min Safety Stock Days (expanded)	0.00	0.00	0.00	0.00
Store Min Safety Stock Units (expanded)	0.00	0.00	0.00	0.00
Store Min Stock (expanded)	0.00	0.00	0.00	0.00
Store Min Time Supply Days (expanded)	0.00	0.00	0.00	0.00
Store MSQ Constraint Indicator (expanded)	On	On	On	On
Store Net Inventory	0.00	0.00	0.00	0.00
Store Ordering Pack Size				
Store Percent of Pallet (expanded)	0.00	0.00	0.00	0.00
Store Projected Inventory	0.00	0.00	0.00	0.00
Store Promotion Presentation Stock	0.00	0.00	0.00	0.00
Store Promotion Presentation Stock Override Flag (expanded)	Off	Off	Off	Off
Store Receipt Plan	0.00	0.00	0.00	0.00
Store Receipt Point	0.00	0.00	0.00	0.00
Store Receive Up to Level	0.00	0.00	0.00	0.00
Store Reconciled Orders	☐	☐	☐	☐
Store Reconciliation Adjustment	0.00	0.00	0.00	0.00
Store Release Schedule				

SRP Replenishment Summary (SKU/Store/Day) Worksheet

The following measures appear automatically when using the default template. All measures are read only.

Measure Label	Description
Base Store Promotion Presentation Stock	The Base Store Promotion Presentation Stock represents the specified quantity for Store Promotion Presentation Stock before application of the End of Store Promotion Factor.
Daily Store Standard Deviation	The Daily Store Standard Deviation represents the forecast error assuming a normal distribution. The standard deviation is used in the calculation of dynamic safety stock. Note: This measure is loaded from an external system.
End of Store Promotion Factor (expanded)	The expanded version of End of Store Promotion Factor will display the actual value used in the calculations. This version will display a factor of 1 for the days within the promotion period prior to the ramp down and will then show the designated End of Promotion Factor values as it approaches the end of the promotion. A factor of 1 will be displayed after the promotion has ended.
Projected Stock Out	Projected Stock Out is calculated based on forecasted demand and projected inventory. Note: This measure is information only. It is used in the High Projected Out of Stock Alert.

Measure Label	Description
Store Available To Plan Receipt	The Store Available To Plan Receipt (ATP) indicates the days on which a store may plan a receipt based on the store's release schedule. A checkmark in a box indicates a receipt may be planned on that day.
Store AWS Factor (expanded)	The AWS Factor allows SRP users to provide a numeric factor to be multiplied against the average weekly sales (AWS) to determine replenishment boundaries (safety stock, receipt point and receive up to level) for the Factor AWS replenishment method. Example: An AWS Factor of .5 will calculate a safety stock that is 50% of the average weekly sales. The expanded version of Store AWS Factor will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered.
Store Boundary Stock (expanded)	The Boundary Stock identifier allows SRP users to select the stock level to use in calculating the Store Receipt Point and Store Receive Up to Level. This stock level is a combination of Safety Stock, Presentation Stock and/or Promotional Presentation Stock based on the identifiers listed below. If the identifier contains "vs.", the greater value will be used. This parameter affects all replenishment methods. The boundary options are: - SS vs PS + PPS - SS vs PS - SS vs PPS - SS + PS + PPS - SS + PS - SS + PPS - SS Where, - SS = Safety Stock - PS = Presentation Stock - PPS = Promotional Presentation Stock The default is SS vs PS + PPS. Example: SS vs PS will add the greater of SS or PS to the calculated Store Receipt Point and Store Receive Up to Level values. SS + PS will add the total of SS and PS to the calculated Store Receipt Point and Store Receive Up to Level values. The expanded version of Store Boundary Stock will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered.
Store Customer Orders	Store Customer orders (CO) are orders placed by customers at a store for a specific quantity of a SKU to be picked up on a specific delivery date. Customer orders are treated as additional demand on top of normal forecasted demand. Note: Customer Orders are loaded to SRP from an external system.

Measure Label	Description
Store Customer Orders Over Review Time	Store Customer Orders Over Review Time represents the customer Orders that must be accounted for when calculating the ideal receipt quantity on an ATP day. Customer Orders are summed from the day after the beginning of the review period through the day before the end of the review period. Store Customer Orders Over Review Time is only calculated on Available to Plan receipt days.
Store Demand Forecast	The Store Demand Forecast is the forecast of the store's future sales. Note: Demand Forecast is loaded from an external forecasting system.
Store Demo Stock (expanded)	Amount of stock that is used as demonstration product, but is still available to sell. Demo Stock is added to the RP and RUTL levels for each day. The expanded version of Store Demo Stock will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered.
Store Expected Receipts	Store Expected Receipts (ER) are orders that have already been executed and therefore need to be considered when planning future orders for a store. Store Expected Receipts is the sum of in-transits and on orders. Note: In-transits and on orders s are loaded to SRP from an external system.
Store Forecast Demand Over Review Time	The Store Forecast Demand Over Review Time is calculated as the sum of the forecasted demand from the current day through the next receipt day. Store Forecast Demand Over Review Time is only calculated on Available to Plan receipt days.
Store Increment Percent (expanded)	The Increment Percent acts as a multiplier for minimum and maximum stock that is designed to handle temporary fluctuation in demand for items using the Min/Max Replenishment Method. An increment percentage factor can be used to temporarily increase or decrease targeted stocking levels without altering the established MIN and MAX values. Example: An Increment Percent of 1.2 will add 20% to the Min and Max Stock. The expanded version of Store Increment Percent will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered.

Measure Label	Description
Store Inventory Selling Days (expanded)	The Inventory Selling Days parameter is used to specify the number of days of forecast quantity to be used when calculating the Receive up to Level (RUTL) with the Hybrid, Dynamic, Poisson and Loaded SS Dynamic Replenishment Methods. The RUTL calculation will use the forecast demand over the greater of Inventory Selling Days and Review Time. Inventory Selling Days can be used to avoid producing very small frequent orders. Example: Inventory Selling Days of 14 ensures an order will contain at least 14 days of supply. The expanded version of Store Inventory Selling Days will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered.
Store Max Safety Stock Days (expanded)	The Max Safety Stock Days parameter is used to specify the maximum number of days of cover to be kept on hand as safety stock. If the user enters both Max Safety Stock Days and Max Safety Stock Units, the maximum safety stock boundary will use the larger of demand over max safety stock days and max safety stock units. Example: Max Safety Stock Days of 14 ensures the maximum safety stock will contain at least 14 days of supply. If Max Safety Stock Units is greater than 14 days of supply, max units would be used as the maximum safety stock, otherwise maximum safety stock would be the number of units required to cover 14 days of demand, calculated as the sum of demand over the next 14 days beginning with the current day. The expanded version of Store Max Safety Stock Days will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered.
Store Max Safety Stock Units (expanded)	The Max Safety Stock Units parameter is used to specify the maximum amount of inventory to be kept on hand as safety stock. If the user enters both Max Safety Stock Days and Max Safety Stock Units, the maximum safety stock boundary will use the larger of demand over max safety stock days and max safety stock units. Example: Max Safety Stock Days of 14 ensures the maximum safety stock will contain at least 14 days of supply. If Max Safety Stock Units is greater than 14 days of supply, max units would be used as the maximum safety stock, otherwise maximum safety stock would be the number of units required to cover 14 days of demand. The expanded version of Store Max Safety Stock Units will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered.
Store Max Stock (expanded)	Max Stock is only used in the Min/Max Replenishment Method. It represents the maximum stock level in units that are desired on hand to satisfy demand. The receipt plan quantity is calculated to bring Net Inventory up to MAX Stock. The expanded version of Store Max Stock will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered.

Measure Label	Description
Store Max Time Supply Days (expanded)	Max Time Supply Days is only used in the Time Supply Replenishment Method. It represents maximum stock level in terms of number of days cover that that are desired on hand to satisfy demand. The receipt plan quantity is calculated to bring Net Inventory up to Maximum Time Supply Days of cover. Example: Max Time Supply Days of 14 ensures an order will bring the inventory level up to 14 days of supply. The expanded version of Store Max Time Supply Days will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered.
Store Min Safety Stock Days (expanded)	The Min Safety Stock Days parameter is used to specify the minimum number of days of cover to be kept on hand as safety stock. If the user enters both Min Safety Stock Days and Min Safety Stock Units, the minimum safety stock boundary will use the larger of demand over min safety stock days and min safety stock units. Example: Min Safety Stock Days of 7 ensures the minimum safety stock will contain at least 7 days of supply. If Min Safety Stock Units is greater than 7 days of supply, min units would be used as the minimum safety stock, otherwise minimum safety stock would be the number of units required to cover 7 days of demand, calculated as the sum of demand over the next 7 days beginning with the current day. The expanded version of Store Min Safety Stock Days will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered.
Store Min Safety Stock Units (expanded)	The Min Safety Stock Units parameter is used to specify the minimum amount of inventory to be kept on hand as safety stock. If the user enters both Min Safety Stock Days and Min Safety Stock Units, the minimum safety stock boundary will use the larger of demand over min safety stock days and min safety stock units. Example: Min Safety Stock Days of 7 ensures the minimum safety stock will contain at least 7 days of supply. If Min Safety Stock Units is greater than 7 days of supply, min units would be used as the minimum safety stock, otherwise minimum safety stock would be the number of units required to cover 7 days of demand. The expanded version of Store Min Safety Stock Units will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered.
Store Min Stock (expanded)	Min Stock is only used in the Min/Max Replenishment Method. It represents the minimum stock level in units that are desired on hand to satisfy demand. Min Stock is used in determining the inventory level at which a replenishment is triggered. The expanded version of Store Min Stock will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered.

Measure Label	Description
Store Min Time Supply Days (expanded)	Min Time Supply Days is only used in the Time Supply and Hybrid Replenishment Method. It represents minimum stock level in terms of number of days cover that that are desired on hand to satisfy demand. Min Time Supply Days of cover is used in both safety stock and receipt point calculations. Example: Min Time Supply Days of 7 ensures a minimum inventory level that will cover 7 days of supply. The expanded version of Store Min Time Supply Days will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered.
Store MSQ Constraint Indicator (expanded)	The expanded version of Store MSQ Constraint Indicator displays the actual value used in calculations. This represents the merge of the global default, default, and exception level versions of Store MSQ Constraint Indicator. If the indicator is "On", MSQ will be applied as a constraint during ordering decisions.
Store Net Inventory	Store Net Inventory (NI) is calculated in batch AIP and is a prediction of the inventory position at the end of review time. It represents what inventory will be available to meet demand over the period. The NI calculation is based on the Projected Inventory position at the beginning of the period, then considering the impact of expected receipts and expected spoilage (ER & ES) over the review time. Store Net Inventory is only calculated on Available to Plan receipt days, and is used as the point at which SRP will generate a planned receipt.
Store Ordering Pack Size	The Store Ordering Pack Size represents the primary pack size to be used when ordering a SKU for a store (either from a warehouse or from a supplier). Note: Store Ordering Pack Size is loaded from Data Management online (DMo).
Store Percent of Pallet (expanded)	Percent of pallet is used to determine if the Ideal Receipt Quantity for replenishment should be rounded to a full pallet. It represents the percentage threshold that case demand must exceed in order for pallet rounding to occur. Example: Percent of Pallet of .75 will round an order up to a pallet if the case demand is greater than 75 percent of a pallet. The expanded version of Store Percent of Pallet will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered.
Store Projected Inventory	Store Projected Inventory (PI) is calculated in AIP batch and represents a projection of the opening inventory position for any day in the planning horizon at a specific store. None of that day's activities (either receipts or demand) are reflected in PI, and so it is often referred to as a "beginning of day" position. PI on a given day is calculated as the PI of the previous day plus the net impact of all demand and replenishments on the previous day. Previous day demand is consists of forecasted demand plus any customer orders (CO) on that day. Previous day replenishments consist of Expected and Planned Receipts.

Measure Label	Description
Store Promotion Presentation Stock	The Store Promotion Presentation Stock represents the End of Store Promotion Factor applied to the Base Store Promotion Presentation Stock. If the Store Promotion Presentation Stock Override Flag is turned on, this becomes equal to zero ("0").
Store Promotion Presentation Stock Override Flag (expanded)	The expanded version of Store Promotion Presentation Stock Override Flag will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered.
Store Receipt Plan	The Store Receipt Plan represents SRP's recommendations for ordering based on demand, allocation boundaries and available inventory. The Receipt Plan is final result calculations in AIP Batch including adjustments made to Ideal Receipt Quantity based on rounding and constraints made to the unconstrained receipt plan based on inventory available at the source.
Store Receipt Point	The Store Receipt Point (RP) represents the inventory level below which an order should be triggered. Receipt point is calculated differently based on the selected Replenishment Method. Store Receipt Point is only calculated on Available to Plan receipt days.
Store Receive Up to Level	The Receive Up To level (RUTL) denotes the target level of inventory when generating an order. Receive Up To Level is calculated differently based on the selected Replenishment Method. Store Receive Up to Level is only calculated on Available to Plan receipt days.
Store Reconciled Orders	The Store Reconciled Orders is an indicator informing users which indicates which orders have been reconciled.
Store Reconciliation Adjustment	The Store Reconciliation Adjustment represents the difference between the Unconstrained Receipt Plan and the Store Receipt Plan due to inventory constraints, inventory availability at the source location.
Store Release Schedule	The Store Release Schedule is an integer representing the lead time from a source location to store for a SKU. The release schedule is calculated in Data Management (DM) based on lead time and order cycle. A numeric field indicating the lead times.

Measure Label	Description
Store Repl Method (expanded)	The choice of Replenishment Method determines the calculations that will be used in generating a store replenishment method. The Replenishment Method options are: - Min/Max - Time Supply - Dynamic - Hybrid - No Replenishment - Poisson Replenishment - Loaded SS Dynamic - Sales Week Range - Factor AWS The default is No Replenishment. The expanded version of Store Repl Method will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered.
Store Rounding Method (expanded)	The Rounding Method is used when pack rounding the ideal receipt quantity (IRQ). The Rounding Method options are: - Order Pack - Normal The expanded version of Store Rounding Method will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered.
Store Rounding Threshold (expanded)	The Rounding Threshold represents the portion of a pack above which the replenishment plan is rounded up and below which it is rounded down. Example: A Rounding Threshold of .25 will to round an order up to a pack if the demand is greater than 25 percent of a pack. The expanded version of Store Rounding Threshold will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered.
Store Safety Stock	Store Safety Stock (SS) is inventory held at a location to mitigate the risks of stock outs caused by variability in forecasted demand. Safety stock is calculated differently based on the selected Replenishment Method. All replenishment methods allow the safety stock to be bound by minimum and maximum values. Store Safety Stock is only calculated on Available to Plan receipt days.

Measure Label	Description
Store Safety Stock Level Factor (expanded)	The Safety Stock Level Factor represents the amount of additional safety stock to carry in anticipation of unpredictable events (for instance, weather changes) or to provide additional safety stock during a special promotion or event. This will provide a temporary lift in the Receipt Point (RP) and Receive Up To Level (RUTL) values. The Safety Stock Level Factor is used in Time Supply, Hybrid, Poisson, Dynamic and Loaded SS Dynamic Replenishment Methods. Example: To increase safety stock by 25 units, the user would enter a Safety Stock Level Factor of 25. Negative values may also be entered to decrease the safety stock level. The expanded version of Store Safety Stock Level Factor will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered.
Store Service Level (expanded)	The Service Level is used in the safety stock calculations for the Dynamic and Poisson replenishment methods. It is defined as the percentage of time that the stock should be able to meet demand. Example: A Service Level of .90 will carry enough safety stock to maintain a 90% customer service level. The expanded version of Store Service Level will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered.
Store Shelf Capacity (expanded)	Shelf capacity is the amount of stock to fill a shelf to the desired maximum level. If the Shelf Capacity Flag is set to 'Yes', the shelf capacity is used to cap the receipt point and receive up to level. The expanded version of Store Shelf Capacity will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered.
Store Shelf Capacity Flag (expanded)	The Shelf Capacity Flag is used to determine if the receipt point and receive up to level should be capped by the shelf capacity. The Shelf Capacity Flag options are: Yes No Example: 'Yes' will cause SRP to use shelf capacity to cap receipt point and receive up to level. For 'No' or Default' SRP will not use shelf capacity to cap receipt point and receive up to level. The expanded version of Store Shelf Capacity Flag will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered.
Store Source Label	The Store Source Label identifies the source from which this store receives inventory.

Measure Label	Description
Store Time Supply Horizon (expanded)	The Time Supply Horizon parameter is used to specify days of forecast in order to calculate a rate of sale. If a time supply horizon is specified, the rate of sale is used instead of the actual forecast when calculating demand over the time supply days for inventory target level calculations for the Time Supply Replenishment Method. Example: A Time Supply Horizon of 7 will calculate a Rate of Sale (ROS) over a one week period. The (ROS) is then calculated by summing the forecasted sales over the 7 days and dividing that number by 7. The expanded version of Store Time Supply Horizon will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered.
Store Weekly Sales Max (expanded)	Maximum stock boundary for the Factor AWS, Sales Date Range, and Loaded SS Dynamic replenishment methods. The expanded version of Store Weekly Sales Max will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered.
Store Weekly Sales Min (expanded)	Minimum stock boundary for the Factor AWS, Sales Date Range, and Loaded SS Dynamic replenishment methods. The expanded version of Store Weekly Sales Min will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered.
User Specified Store Presentation Stock (expanded)	User Specified Store Presentation Stock is the minimum amount of stock in units desired to have on hand for display/sales purposes. User Specified Store Presentation Stock may be taken into consideration when calculating the Receipt Point and Receive up to Level, depending on the Boundary Stock selected. The expanded version of User Specified Store Presentation Stock will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered.

Hidden Workbook Measures

The following measures are hidden when using the default template. They can be displayed and maintained by using the Insert measure function of RPAS. Hidden measures may also be added to the template during configuration.

Measure Label	Description
Active SKU CAP (Expanded)	SKU Cap value (in units) that is used in store replenishment calculations. During replenishment calculations, this is the maximum boundary for inventory at the store.
Cases Per Pallet	Cases Per Pallet reflects the number of cases on a pallet. Note: Cases Per Pallet is loaded from Data Management online (DMo).
Daily Sales	Daily Sales represents the daily sales for a SKU/Store/Day. Note: This measure is loaded from an external system for use in calculating SRP alerts.
Store Acceptable Loss (expanded)	Store Acceptable Loss represents the percentage of a case that is acceptable to lose from spoilage in order to prevent stock outs. This measure is used when rounding ideal receipt quantities. Store Spoilage Threshold is calculated as 1 minus Store Acceptable Loss. Example: Store Acceptable Loss of .25 means it is acceptable to lose 25% of a case from spoilage. In this case, spoilage threshold would be calculated as .75, but only acceptable loss would be updated in the database. The expanded version of Store Acceptable Loss will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered.
Store Ads Grand Opening	Store Ads Grand Opening indicates grand opening ads exist for this SKU/Store/Day. This measure can be aggregated to provide information regarding the number of locations that are on Ad. Note: This measure is loaded from an external system.
Store Ads Inserts	Store Ads Inserts indicates inserts ads exist for this SKU/Store/Day. This measure can be aggregated to provide information regarding the number of locations that are on Ad. Note: This measure is loaded from an external system.
Store Ads Others	Store Ads Others indicates other miscellaneous ads exist for this SKU/Store/Day. This measure can be aggregated to provide information regarding the number of locations that are on Ad. Note: This measure is loaded from an external system.
Store Ads Run on Press	Store Ads Run on Press indicates run on press ads exist for this SKU/Store/Day. This measure can be aggregated to provide information regarding the number of locations that are on Ad. Note: This measure is loaded from an external system.
Store Available Space	Store Avail Space represents the remaining space available under the SKU Cap after considering Store Inventory and Expected Receipts over the appropriate time period(s).

Measure Label	Description
Store Avg Rate of Sale	Store Avg Rate of Sale represents an item's average daily rate of sale at a store. Note: This measure is loaded from an external system at the SKU/Store level and spread to the SKU/Store/Day level across the planning horizon.
Store Capped Difference	The Store Capped Difference is equal to Non-Capped URP – URP on any ATP day.
Store Demand on Source	The Store Demand on Source is equal to the URP time-shifted backwards based on the lead-time on the receipt day of the URP into the store.
Store Expected Spoilage	Expected Spoilage refers to a quantity of a SKU at a store whose product life expires and therefore becomes un-sellable at the end of a day. Expired quantities can not be used for any sales after the day they expire. Expected spoilage is only calculated when the global Inventory Aging Flag is set to true, the Product Life of the SKU is greater than zero and the Product Life of the SKU is less than or equal to the Aging Threshold. The calculation is based on the inventory position, demand, expected receipts and product life. The user can specify an expected write-off quantity which will override the expected spoilage if the write-off quantity is greater than the calculated value.
Store Expected Write-off	Store Expected Write-off represents the quantity of stock expected to be thrown out for any reason (spoilage, breakage, etc.) on a given day. Expected Write-offs override calculated expected spoilage. Note: This measure is loaded from an external system.
Store Intransits	Store Intransits represents Inventory in transit from warehouses and suppliers to store. Note: This measure is loaded from an external system.
Store Known Demand	Store Known Demand is the quantity in units of confirmed demand that is known for any reason. Known demand is used in place of the forecast if the known demand is greater than the forecast. Note: This measure is loaded from an external system.
Store Loaded Safety Stock History	Store Loaded Safety Stock History maintains history of the Loaded safety stock measure. Note: This measure is loaded from an external system.
Store Maximum Sellable Quantity	Store Maximum Sellable Quantity (MSQ) represents a level of inventory that can be sold within the life of a product. It is calculated as all forecast demand over the product life starting from the beginning of the review time. Customer orders over the review time (CORT) are then added. Store Maximum Sellable Quantity is only calculated on Available to Plan receipt days. As MSQ is dependent upon Product Life (PL), where Product Life is deemed to be not relevant for a SKU, the MSQ is considered infinite (Unbounded).

Measure Label	Description
Store Minimum Sales Stock	Store Minimum Sales Stock (MSS) represents a level of inventory required to meet demand. This is calculated as forecast demand over the review time. Customer orders over the review time (CORT) are then added. For those replenishment methods where forecasted demand is not used, demand in the MSS calculation is replaced with calculated Safety Stock. Store Minimum Sales Stock is only calculated on Available to Plan receipt days. If a shelf capacity constraint exists (Shelf Capacity Flag is set to true) Store Minimum Sales Stock may not exceed the level required to fill the shelf to capacity and meet CORT.
Store Non-Capped Demand on Source	The Store Non-Capped Demand on Source is equal to the Non-Capped URP time-shifted backwards based on the lead-time on the receipt day of the URP into the store.
Store Non-Capped URP	Store Non-Capped URP represents the theoretical URP at the SKU/Store/day level, which would have been calculated if the SKU was not capped at all across time.
Store Numeric In Scope Indicator	Store Numeric In Scope Indicator is used in SRP alert processing to determine the alerting store ratio. It represents the number of stores for a SKU that are 'in-scope' (stores which fall between on supply and off supply) during the alert horizon.
Store On Orders	Store On Orders are fixed orders currently being processed for delivery to store either from warehouses or directly from suppliers Note: This measure is loaded from an external system.
Store Placed CRP	Store Placed CRPs are planned orders generated within the placement lead-time. They represent receipt plans previously generated but not released. These CRPs will not be deleted or changed within the placement lead-time, but will be saved for release on the future release date.
Store Placed Orders	Store Placed Orders indicates which orders have been placed. Once an order is placed, it cannot be changed within the store placement lead-time, unless a USA is raised. Placed orders can be generated from a User Specified Allocation (USA) or during the nightly batch process when the store has a longer placement lead time than release schedule.
Store Placement Schedule	The Store Placement Schedule defines the time required by the supplier to plan for an order and the lead-time to get the order to the store. Once an order is placed, it cannot be changed within the store placement lead-time, unless a USA is raised. The Store Placement Schedule must be a valid release date based on the Store Release Schedule greater than the release schedule. The Store Placement Schedule is calculated in Data management (DM).
Store Product Life	Store Product Life represents the number of days from the time a product arrives at the store until it spoils.

Measure Label	Description
Store Recommended Coupled Flag	The Store Recommended Coupled Flag coupled flag is an information only flag to indicate a placement lead-time is recommended for this SKU. The coupled flag is not used in any calculations and does not determine that the placement lead-time is used. TRUE means recommended coupled orders. FALSE means recommended decoupled orders. Note: This measure is loaded from Data Management online (DMo).
Store Review Time	Store Review Time is a calculated measure indicating the number of days until the next delivery. Store Review Time is only calculated on Available to Plan receipt days.
Store Spoilage Threshold (expanded)	Spoilage threshold is a threshold used as a pack rounding constraint. Ideal receipt quantities will be rounded up if they exceed the spoilage threshold. Store Acceptable Loss is calculated as 1 minus Store Spoilage Threshold. Example: A Store Spoilage Threshold of .75 will round a planned receipt down a case when less than 75% of the case is expected spoilage. In this case, acceptable loss would be calculated as .25 and acceptable loss would be updated in the database. The expanded version of Store Spoilage Threshold will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered.
Store Supplier Compliance Safety Stock Uplift	Store Supplier Compliance Safety Stock Uplift represents additional safety stock units added to the calculated safety stock. The Supplier Compliance Safety Stock Uplift is calculated as a number of days of demand going forward from the larger of review time or number of inventory selling days.
Store USA Over Review Time	Store USA Over Review Time (USART) is the sum of User Specified Allocations over the review time. Store USA Over Review Time is only displayed on Available to Plan receipt days.
Store USA Over Review Time Type	The Store USA Over Review Time Type measure indicates the allocation combination type that is used when regarding the USART quantity as a whole. The first populated USA type in the review time is used as the USART type. Store USA Over Review Time Type Time is only displayed on Available to Plan receipt days.
Store User Specified Allocation	Store User Specified Allocations (USA) are allocations that are defined by the user and accounted for in projected inventory. USAs are maintained in the USA workbooks.

SRP Replenishment Plan (SKU/Store/Week) Worksheet

	04/29/06	05/06/06	05/13/06	05/20/06
Actual Weekly Sales	0.00	0.00	0.00	0.00
Store Roll Weeks (expanded)	No	No	No	No

SRP Replenishment Plan (SKU/Store/Week) Worksheet

The following measures are included in this worksheet and displayed automatically when using the default template. All measures are read only.

Measure Label	Description
Actual Weekly Sales	Actual Weekly Sales is used in Sales Week Range and Factor AWS replenishment methods. It represents the actual historical sales by week for a SKU/Store. As a default, SRP maintains the last 52 weeks of history (purge age is set to 371 days). This ensures that the oldest week of history is automatically dropped as each new week of sales history is added. Note: Actual Weekly Sales is loaded to SRP from an external system.
Store Roll Weeks (expanded)	The Roll Weeks parameter indicates whether SRP logic should automatically roll the start and end date range settings forward one week or not. Roll weeks is used in the Factor AWS Sales Date Range Replenishment Methods. The Roll Weeks options are: - Yes - No - Default Example: 'Yes' will cause the start and end date to roll forward one week, allowing the user to keep the weekly historical sales at the same relative distance in the past. 'No' will not move the start and end date forward allowing the user to use the same weekly historical sales as the system moves forward in time. The expanded version of Store Roll Weeks will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered.

Measure Label	Description
Actual Weekly Sales	Actual Weekly Sales is used in Sales Week Range and Factor AWS replenishment methods. It represents the actual historical sales by week for a SKU/Store. As a default, SRP maintains the last 52 weeks of history (purge age is set to 371 days). This ensures that the oldest week of history is automatically dropped as each new week of sales history is added. Note: Actual Weekly Sales is loaded to SRP from an external system.

SRP Replenishment Plan (SKU/Store) Worksheet

SRP Replenishment Plan (SKU/Store) Worksheet

The following measures are included in this worksheet and displayed automatically when using the default template. All measures are read only.

Measure Label	Description
Like SKU	Like SKU allows the SRP user to select a similar SKU to obtain sales history from for new SKUs or SKUs with scant historical data. The new SKU will use the Like SKUs history until the Like SKU End Date when the new SKU has built up stable sales history. The Like SKU's sales history is used in the RP and RUTL boundaries for a new SKU using the Sales Week Range or Factor AWS replenishment method.
Like SKU End Date	The Like SKU End Date parameter allows SRP users to select the date that should be used as the ending point for using the Like SKUs sales history in calculations for the "Sales Date Range" and "Factor AWS" replenishment methods.

Measure Label	Description
Off-Supply Effective Date	The Off-Supply Effective Date represents the date a store should stop receiving the product. Note: The Off-Supply Effective Date is loaded from Data Management online (DMo).
On-Supply Effective Date	The On-Supply Effective Date represents the date a store should begin receiving the product. Note: The On-Supply Effective Date is loaded from Data Management online (DMo).
Projected Stock Out	Projected Stock Out is calculated based on forecasted demand and projected inventory. Note: This measure is information only. It is used in the High Projected Out of Stock Alert.
RDF Detail Alert Count	The RDF Detail Alert Count represents the number of alert hits from a forecasting system for this SKU/Store. This allows the SRP User to consider if action needs to be taken in the forecasting system to correct a problem prior to making changes to any SRP parameters. Note: The RDF Detail Alert Count is loaded from an external system.
SRP RDF Detailed Alert	The SRP RDF Detailed Alert indicates an RDF alert exists for this SKU/Store.
Store Current Inventory	Store Current Inventory represents the store's on hand position inventory position. Note: Current Inventory is loaded from an external system. Negative values are rejected by SRP and replaced with a zero. There is a contingency process in the event that the load from a store fails. It will provide SRP with a system generated current store inventory value for its replenishment calculations. The calculations starts with yesterdays projected inventory position and adds in the difference between actual sales and forecasted demand.
Store End Date Range (expanded)	The End Date Range parameter allows SRP users to select the date that should be used as the ending point for determining the historical sales data used by the "Sales Date Range" and "Factor AWS" replenishment methods. In the Sales Date Range method, the date range is the period over which sales history is summed. In the Factor AWS method, it is the time period over which average weekly sales is calculated. The expanded version of Store End Date Range will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered.
Store Repl Subtype Code	Store Repl Subtype Code represents user defined replenishment subtype codes. These codes are display only and are not used in any calculations. Note: Store Repl Subtype Code is loaded from an external system.
Store Repl Type Code	Store Repl Type Code represents user defined replenishment subtype codes. These codes are display only and are not used in any calculations. Note: Store Repl Type Code is loaded from an external system.

Measure Label	Description
Store Start Date Range (expanded)	The Start Date Range parameter allows SRP users to select the date that should be used as the starting point for determining the historical sales data used by the "Sales Date Range" and "Factor AWS" replenishment methods. In the Sales Date Range method, the date range is the period over which sales history is summed. In the Factor AWS method, it is the time period over which average weekly sales is calculated. The expanded version of Store Start Date Range will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered.
Use Like SKU	Use Like SKU indicates whether or not the Like SKU will be used to obtain sales history in the RP and RUTL boundary calculations when using the Sales Week Range or Factor AWS replenishment method. Use Like SKU can be True or False. The default is False.

Hidden Workbook Measures

The following measures are hidden when using the default template. They can be displayed and maintained by using the Insert measure function of RPAS. Hidden measures may also be added to the template during configuration.

Measure Label	Description
Store Freshness Flag (expanded)	The Freshness Flag is only used when the Inventory Aging Limit is set (indicating the SKU has a product life). When the Freshness Flag is "TRUE," SRP will ensure that a store replenishment plan is generated for at least the customer orders over Review Time (CORT) regardless of the inventory position. The Freshness Flag options are: - On - Off - Default The expanded version of Store Freshness Flag will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered.
Store Loaded Safety Stock	Store Loaded Safety Stock represents safety stock value used when using Loaded SS Dynamic replenishment method. Note: This measure is loaded from an external system.
Store Supplier Compliance Safety Stock (expanded)	The Supplier Compliance Safety Stock parameter represents a 'number of days of supply' additional safety stock to deal with supplier and supply chain compliance issues. The days covered begins with the latest of Review Time or Inventory Selling Days. The calculated Supplier Compliance Safety Stock Units is added on to the Safety Stock. Example: Supplier Compliance Safety Stock of 7 adds an addition 7 days of supply to the safety stock. The expanded version of Store Supplier Compliance Safety Stock will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered.

SRP Replenishment Plan Parameters (Store) Worksheet

SRP Replenishment Plan Parameters (Store)

Location: S303 - MISHAWAKA IN

Sister Store	
Sister Store Parameters Flag	☐
Store Open Date	

Measure: < [List of Measures] >

SRP Replenishment Plan Parameters (Store) Worksheet

The following measures are included in this worksheet and displayed automatically when using the default template. The loaded and calculated measures are read only.

Measure Label	Description
Sister Store	A Sister Store allows the user to model a new store after a store with similar characteristics and anticipated similar sales. To do this, a "Sister Store" relationship is set up in RMS. Once this relationship is established, AIP will perform a one-time copy of all required replenishment settings and parameters from the sister store. AIP will perform a weekly copy of sales history from the sister store to a new store that is scheduled to open. It will continue to copy the sales history weekly up until the Store Opening Date.
Sister Store Parameters Flag	The Sister Store Parameters Flag Indicates that a sister store has had all store parameters copied from its sister store to itself. Note: This measure is loaded from Data Management online (DMo).
Store Open Date	Store Open Date is used in sister store copy; sales history from the sister store is copied to the new store until the new store reaches its opening date. Note: This measure is loaded from Data Management online (DMo).

SRP Replenishment Plan Parameters (SKU) Worksheet

SRP Replenishment Plan Parameters (SKU) Worksheet

Reconciliation Method is the only measure in this worksheet.

Measure Label	Description
Reconciliation Method	The Reconciliation Method is used to determine if reconciliation will occur on a day by day basis or over time. The Reconciliation Method options are: - Day-on-Day - Reconcile Over Time Example: Selecting 'Day-on-Day' will cause reconciliation from the source warehouse or supplier to occur for each day in the planning horizon. Day-on-Day reconciliation will ship the inventory out to the store or warehouse destination quickly, considering only those destination stores or warehouses where a shipment today would arrive on the available to plan (ATP) day. While this method may ship the inventory sooner than the 'Reconcile Over Time' method, stores or warehouses with ATP days later in the review period may receive less inventory than those with ATP days earlier in the review period. Selecting 'Reconcile Over Time' will cause reconciliation from the source warehouse or supplier to occur over each review period in the planning horizon. Reconcile Over Time allocation may cause some inventory to be retained at the source warehouse or supplier for shipment later in the review period. While this method may not ship the inventory as quickly as the 'Day-on-Day' method, all ATP days within the review period for all stores and warehouses will be considered equally in the inventory allocation.

WH Inventory Analysis (SKU Group/Warehouse/Day) Worksheet

This worksheet contains aggregate warehouse inventory information for review and inventory analysis purposes.

	04/01/06	04/02/06	04/03/06	04/04/06
Store Projected DOS	0.00	0.00	0.00	0.00
Total Store Average Daily Sales	0.00	0.00	0.00	0.00
WH Expected Receipts	0.00	0.00	0.00	0.00
WH Projected DOS	0.00	0.00	0.00	0.00
WH Projected Inventory	0.00	0.00	0.00	0.00
WH Total ARS	0.00	0.00	0.00	0.00

WH Inventory Analysis (SKU Group/Warehouse/Day) Worksheet

The following measures appear automatically when using the default template. All measures are read only.

Measure Label	Description
Store Projected DOS	Projected Days of Stock at the store indicates the total number of days of supply on-hand at stores on a given day for all stores sourced from a given warehouse. Store Projected DOS is calculated by summing the Store Projected Inventory measure for all stores sourced from a given warehouse and dividing that sum by the Total Store Avg Daily Sales.
Total Store Average Daily Sales	Total Store Average Daily Sales represents the sum of the daily Average Rate of Sale (ARS) for a given SKU on a given day for all the stores that are sourced from a given warehouse. Average Rate of Sale (ARS) is calculated by dividing the weekly ARS by 7. Weekly ARS is an external load.
WH Expected Receipts	WH Expected Receipts represents the total warehouse expected receipts for the store's source warehouse.
WH Projected DOS	WH Projected DOS at the warehouse indicates the total number of days of supply on-hand at the warehouse on a given day. WH Projected DOS is calculated in AIP Batch at SKUG/WH/Day level by taking the WH Projected Inventory divided by the WH Total Average Daily Sales.
WH Projected Inventory	WH Projected Inventory (PI) represents a projection of the opening inventory position for any day in the planning horizon at the warehouse. None of that day's activities (either receipts or demand) are reflected in PI, and so it is often referred to as a "beginning of day" position.
WH Total ARS	WH Total ARS represents the Total Store Avg Daily Sales and WH Independent ARS. It is calculated by adding the sum of the store ARS for all stores sourced from a given warehouse to the warehouse independent ARS.

Company Level Inventory Analysis Worksheet

This worksheet provides a company-wide view of inventory levels in the supply chain

Product	04/01/06	04/08/06	04/15/06	04/22/06
100035008B - CALCULATOR,GRAPHING,SILVER				
Actual Weekly Sales	0.00	0.00	0.00	0.00
Actual Weeks Of Supply	0	0	0	0
Ad/Rollout Notes				
Aggregated Store Ads				
Aggregated Store Demo Stock	0.00	0.00	0.00	0.00
Company URP By Week	0.00	0.00	0.00	0.00
End of Week Inventory at Cross Docks	0.00	0.00	0.00	0.00
End of Week Inventory at Deconsolidation Centers	0.00	0.00	0.00	0.00
End of Week Inventory at RDCs	0.00	0.00	0.00	0.00
Expected Receipts from Vendors	0.00	0.00	0.00	0.00
Forecasted Receipts from Vendors	0.00	4000.00	0.00	0.00
Forecasted To Sell-Through %	0.00	0.00	0.00	0.00
Forecasted Weekly Sales	0.00	0.00	0.00	0.00
Forecasted Weeks Of Supply	0.00	0.00	0.00	0.00
Inventory Per Store	0.00	0.00	0.00	0.00

Company Level Inventory Analysis Worksheet

This worksheet contains the following read-only measures.

Measure Label	Description
Actual Weekly Sales	Actual Weekly Sales represents the sum of actual sales data from stores aggregated to the SKU Group/Week level.
Actual Weeks of Supply	Actual Total Weeks of Supply represents weeks of supply for all locations (stores and warehouses). It is calculated by dividing Saleable Inventory by Total Avg Weekly Sales.
Ad/Rollout Notes	SKU Ad/Rollout Notes contains notes related to a product ad or rollout.
Aggregated Store Ads	Aggregated Store Ads indicates the presence of any active ads within the SKU Group/Week level. Aggregated Store Ads is true if at least one ad exists over the week for this SKU Group.
Aggregated Store Demo Stock	Aggregated Store Demo Stock represents the total demo stock over the week for this SKU Group. It is calculated as the sum of demo stock across all stores on the last day of the week (Saturday).
Company URP by Week	Company URP by Week is the unconstrained receipt plan (URP) for a given SKU Group across the company for a given week. Unconstrained receipt plan (URP) is calculated as Store Receipt Plan (SKU/Store/Day) plus the Store Reconciliation Adjustment (SKU/Store/Day). The resulting URP values for each SKU/Store combination are then aggregated to a SKU Group/Company/Week level.

Measure Label	Description
End of Week Inventory at CrossDocks	End of Week Inventory at CrossDocks represents the sum a SKU's Projected Inventory on the last day of the week at all warehouses with a warehouse type of CrossDocks.
End of Week Inventory at Deconsolidation Center	End of Week Inventory at Deconsolidation Center represents the sum of a SKU's Projected Inventory on the last day of the week at all warehouses with a warehouse type of Deconsolidation Center.
End of Week Inventory at RDCs	End of Week Inventory at RDsC represents the sum a SKU's Projected Inventory on the last day of the week at all warehouses with a warehouse type of RDC.
Expected Receipts from Vendors	Expected Receipts from Vendors shows the total inventory on order from vendors to warehouses and stores for any direct to store shipments.
Forecasted Receipts from Vendors	Forecasted Receipts from Vendors shows the total planned receipts from vendors to warehouses and stores for any direct to store shipments.
Forecast to Sell-Through %	Forecast to Sell-Through % contains the percentage of actual sales (historical weekly sales) to forecasted sales (forecasted demand at the week level).
Forecasted Weekly Sales	Forecasted Weekly Sales represents the total forecasted weekly sales (including customer orders) for a given SKU Group.
Forecasted Weeks of Supply	Forecasted Weeks of Supply represents the forecasted weeks of cover. It is calculated by dividing Saleable Inventory by Forecasted Avg Weekly Sales, where Forecasted Avg Weekly Sales is calculated as Forecasted Weekly Sales divided by the Number Of Weeks Forecast.
Inventory per Store	Inventory per Store represents the average inventory level per store, excluding demo stock. It is calculated as the Saleable Inventory divided by the number of stores.
Number Of Stores	Number Of Stores represents the total number of stores for this SKU Group.
Number Of Weeks Forecast	Number Of Weeks Forecast represents the number of weeks in the future (including present week) over which Forecasted Avg Weekly Sales is calculated.
Retail Price	Retail Price is the product's retail price. Note: Retail Price is loaded from an external system.
Saleable Inventory	Saleable Inventory represents the amount of inventory that can actually be sold. It is calculated as the aggregated end of week projected inventory minus the aggregated end of week demo stock.
Sales Week	Sales Week represents the calendar week number. For example, week 5 is the 5th week of the year.
Sum of RDC Avg Weekly Sales	Sum of RDC Avg Weekly Sales contains the aggregated total of average weekly sales for an RDC (Regional Distribution Center) warehouse.
Sum of Stores Avg Weekly Sales	Sum of Stores Avg Weekly Sales contains the aggregation of an item's average weekly sales across all stores.
Total Avg Weekly Sales	Total Avg Weekly Sales contains the Sum of SKU of RDC Avg Weekly Sales and SKU Sum of Stores Avg Weekly Sales.

Measure Label	Description
Tracking Sales	Tracking Sales estimates sales for the current week based on week-to-date sales. First, average daily sales is calculated by dividing the week-to-date sales by the number of days week-to-date (Sunday through the day prior to the current day). Next, the average daily sales are multiplied by 7, resulting in the SKU Tracking Sales.

SRP Exception Summary Tab

SRP Exception Summary (Corporate/SKU) Worksheet

Location	Product
Large Retailers Ltd	100035008 - CALCULATC
	100037020 - PROJECTOR
Ranged Stock Pts	0
Yesterdays Availability	0.00
Yesterdays Forecast	0.00

SRP Exception Summary (Corporate/SKU) Worksheet

This worksheet contains the following read-only measures.

Measure Label	Description
Ranged Stock Pts	Ranged Stock Pts contains the total number of stores across company available to receive and sell items from the previous night's batch run.
Yesterdays Availability	Yesterdays Availability is the percentage of stores across company for which this product was available to sell. In other words the percentage of stores that did not have stock outs the previous night. It is calculated as 1 minus the ratio of stores out of stock last night to the total number of stores available to sell the product.
Yesterdays Forecast	Yesterdays Forecast contains the sum of the forecasted demand for this product for the previous night across all stores (company level).

SRP Exception Summary (Weather Region/SKU) Worksheet

This worksheet allows the user to review alert summary data at the Weather Region/SKU level.

SRP Exception Summary Worksheet (Weather Region/SKU)

This worksheet contains the following read-only measures.

Measure Label	Description
Ranged Stock Pts Weather	Ranged Stock Pts contains the total number of stores across Weather Region available to receive and sell items from the previous night's batch run.
Yesterdays Availability Weather	Yesterdays Availability is the percentage of stores across Weather Region for which this product was available to sell. In other words the percentage of stores that did not have stock outs the previous night. It is calculated as 1 minus the ratio of stores out of stock last night to the total number of stores in this region available to sell the product.
Yesterdays Forecast Weather	Yesterdays Forecast contains the sum of the forecasted demand for this product for the previous night across all stores in this region.

SRP Exception Summary (Store Format/SKU) Worksheet

This worksheet allows the user to review alert summary data at the Store Format/SKU level.

Location	Product
Traditional	100035008 - CALCULATOR 100037020 - PROJECTOR
Ranged Stock Pts Format	0 0
Yesterdays Avail% Format	0.00 0.00
Yesterdays Forecast Format	0.00 0.00

SRP Exception Summary Worksheet (Store Format/SKU)


This worksheet contains the following read-only measures.

Measure Label	Description
Ranged Stock Pts Format	Ranged Stock Pts contains the total number of stores with this format available to receive and sell items from the previous night's batch run.
Yesterdays Availability Format	Yesterdays Availability is the percentage of stores with this format for which this product was available to sell. In other words the percentage of stores that did not have stock outs the previous night. It is calculated as 1 minus the ratio of stores out of stock last night to the total number of stores in this region available to sell the product.
Yesterdays Forecast Format	Yesterdays Forecast contains the sum of the forecasted demand for this product for the previous night across all stores with this format.

Measure Label	Description
Store On Orders	Store On Orders are fixed orders currently being processed for delivery to store either from warehouses or directly from suppliers Note: This measure is loaded from an external system.
Store Ordering Pack Size	The Store Ordering Pack Size represents the primary pack size to be used when ordering a SKU for a store (either from a warehouse or from a supplier). Note: Store Ordering Pack Size is loaded from Data Management online (DMo).
Store Projected Inventory	Store Projected Inventory (PI) is calculated in AIP batch and represents a projection of the opening inventory position for any day in the planning horizon at a specific store. None of that day's activities (either receipts or demand) are reflected in PI, and so it is often referred to as a "beginning of day" position. PI on a given day is calculated as the PI of the previous day plus the net impact of all demand and replenishments on the previous day. Previous day demand is consists of forecasted demand plus any customer orders (CO) on that day. Previous day replenishments consist of Expected and Planned Receipts.
Store Source Label	The Store Source Label identifies the source from which this store receives inventory.

SRP Overstock Alert (SKU) Worksheet

This worksheet allows the user to review pertinent information regarding the SKU's status.



SRP Overstock Alert (SKU) Worksheet

This worksheet contains the following read-only measures.

Measure Label	Description
Corporate Discontinuation Date	The Corporate Discontinuation Date measure indicates the date measure by when the SKU pack size is planned for discontinuation at the corporate level.
Promotional SKU	The Promotional SKU measure denotes whether a SKU is promotional.


SRP Interactive Evaluation Workbook

The SRP Interactive Evaluation workbook is very similar to the SRP Evaluation workbook in that it allows users to review and examine the store replenishment plan. In addition, this workbook provides the capability to perform “what-if” analysis of the replenishment plan and commit any necessary parameter changes.

After making changes to the parameters, the user has the option to recalculate the replenishment portion of the SRP receipt plan (unconstrained) or the replenishment and shortfall reconciliation portions of the SRP receipt plan (constrained). Note, no Substitution, Stockless or SPQ reconciliation will take place. It should be noted that the outcome of the reconciliation will depend on the stores that are included in the workbook. In general, the rule for reconcile should be to perform what if reconciliation analysis on a very small number of products, but for all stores.


In order to utilize the “what-if” functionality in this workbook, enter different parameter variables into any writable measure in the SRP Replenishment Summary worksheet. After making changes to the parameters, the user now has three options:

- Calculate: Clicking on the ‘Calculate’ button in the tool bar will perform calculations of the allocation boundaries (SS, RP and RUTL) only



Oracle Predictive Solutions Menu Bar – Calculate Button

- Selecting ‘What If’, ‘What If – Unconstrained’ on the menu bar will perform the replenishment process across the planning horizon resulting in an unconstrained receipt plan.
- Selecting ‘What If’, ‘What If – Constrained’ on the menu bar will perform the shortfall reconciliation process across the fixed period resulting in a Constrained receipt plan. Note, no Substitution, Stockless or SPQ reconciliation will take place.



Oracle Predictive Solutions Menu Bar – What If Menu

The newly calculated allocation boundaries and receipt plan values will be visible. If users are pleased with the revised plan, they can then commit the new parameter values to the database.

In general, when using ‘What If’ processing, a very small number of products at all stores should be selected for ease of analysis and faster response times.

Like the Evaluation workbook, this workbook contains worksheets that are grouped into three tabs:


- SRP Replenishment Plan – This tab contains the following six worksheets that allow you to review replenishment plan information:
 - SRP Replenishment Summary (SKU/Store/Day)
 - SRP Replenishment Plan (SKU/Store/Week)
 - SRP Replenishment Plan (SKU/Store)
 - SRP Replenishment Plan Parameters (Store)
 - SRP Replenishment Plan Parameters (SKU)
 - WH Inventory Analysis (SKU Group/Warehouse/Day)
 - Company Level Inventory Analysis Worksheet
- SRP Exception Summary – This tab contains the following three worksheets that allow you to examine alert summary data at the specified level:
 - SRP Exception Summary (Weather Region/SKU)
 - SRP Exception Summary (Corporate/SKU)
 - SRP Exception Summary (Store Format/SKU)
- SRP Overstock Alert Summary – This tab contains the following two worksheets that allow you to review details associated with an Overstock:
 - SRP Overstock Details (SKU/Store/Day)
 - SRP Overstock Alert (SKU)

SRP Interactive Evaluation Wizard

Select Ads?

This wizard will not be displayed if the 'Store Ads' measure is not populated or if no ads exist for SKUs within the user's security level.

If the Store Ads measure is populated, the user will first be asked, using radio buttons, whether or not to base the workbook selections on an ad. The 'Store Ads' measure is a Boolean measure at sku/str/ad. The wizard selection will default to "Do Not Use Ads".



SRP Interactive Evaluation Wizard

Build workbook using Ads?

☒ Use Ads

☐ Do Not Use Ads

Cancel <Back Next> Finish Help


SRP Interactive Evaluation Wizard – Use Ads

If the selection is set to "Do Not Use Ads" once the user hits the Next button, the user will be able to select from the Available SKUs. Otherwise, the user will be able to select from Available Ads.

Available Ads

This wizard will not be displayed if the 'Store Ads' measure is not populated or if no ads exist for SKUs within the user's security level.

The dialog box for Available Ads will show a list of all Ads that have at least one true value for a sku/str combination in the AIP domain. The positions default to the Advertisement level. Standard RPAS functionality is available for this particular wizard page.



SRP Interactive Evaluation Wizard – Available Ads

Note: The user can only select one ad. If the user attempts to select more than one ad, he/she will see an error message stating "Only one ad may be selected."

Available SKUs

This wizard will be displayed first if the 'Store Ads' measure is not populated. The dialog box for Available SKUs will show a list of all active SKUs in the AIP domain. A SKU is considered active if, for at least one SKU pack size at a particular destination, the lead time is ≥ 0 for any source on any day within the scheduled horizon.

Also, if the user didn't select any Ads, the dialog box for Available SKUs displayed below will show a list of all active SKUs in the AIP domain. Otherwise, the Available SKUs will be filtered based on the Ads selected. The positions default to the SKU level. Standard RPAS functionality is available for this particular wizard page.

SRP Interactive Evaluation Wizard

Available SKUs

- ☒ 100035008 - CALCULATOR,GRAPHING,SI
- ☒ 100037020 - PROJECTOR VIEWSONIC PJ
- ☐ 100039009 - PAPER,COPY,8.5X11,28#,CC
- ☐ 100061003 - AIP CHAIR,DESK,TOWN,BLA

☐ Synchronize hierarchies

Selected SKUs


- 100035008 - CALCULATOR,GRAPHING,SI
- 100037020 - PROJECTOR VIEWSONIC PJ

Cancel <Back Next> Finish Help

SRP Interactive Evaluation Wizard – Available SKUs

Available Stores


If the user didn't select any Ads, the dialog box for Available Stores displayed below will show a list of all Stores in the AIP domain. Otherwise, the Available Stores will be filtered based on the Ads and SKUs selected. The positions default to the Store level. Standard RPAS functionality is available for this particular wizard page.



SRP Interactive Evaluation Wizard – Available Stores

Available Days

The dialog box for Available Days displayed below will show a list of all Days in the AIP domain. If available, the user's previous selections are already selected. The user has the ability to re-select which dates will be accessed in the workbook. Please note if all days in the scheduled horizon are not selected, workbook calculations may display different values from batch. Standard RPAS functionality is available for this particular wizard page.



SRP Interactive Evaluation Wizard – Available Days

When the user selects 'Finish', the workbook is built using the SKUs, Stores and Days selected.

SRP Replenishment Plan Tab

SRP Replenishment Summary (SKU/Store/Day) Worksheet

	04/01/06	04/02/06	04/03/06	04/04/06
Base Store Promotion Presentation Stock	0.00	0.00	0.00	0.00
Daily Store Standard Deviation	0.00	0.00	0.00	0.00
End of Store Promotion Factor (expanded)	1.00	1.00	1.00	1.00
Projected Stock Out	0.00	0.00	0.00	0.00
Projected Stock Out - What If	0.00	0.00	0.00	0.00
Store Available to Plan Receipt				
Store AWS Factor				
Store AWS Factor (expanded)	0.00	0.00	0.00	0.00
Store Boundary Stock				
Store Boundary Stock (expanded)				
Store Customer Orders	0.00	0.00	0.00	0.00
Store Customer Orders Over Review Time	0.00	0.00	0.00	0.00
Store Demand Forecast	0.00	0.00	0.00	0.00
Store Demo Stock				
Store Demo Stock (expanded)	0.00	0.00	0.00	0.00

SRP Replenishment Summary (SKU/Store/Day) Worksheet

The loaded and calculated measures are read only. Parameter values at the SKU/Store/Day level may be maintained. Expanded measures are read only.

The following measures are displayed automatically when using the default template.

Measure Label	Description
Base Store Promotion Presentation Stock	The Base Store Promotion Presentation Stock represents the specified quantity for Store Promotion Presentation Stock before application of the End of Store Promotion Factor.
Daily Store Standard Deviation	The Daily Store Standard Deviation represents the forecast error assuming a normal distribution. The standard deviation is used in the calculation of dynamic safety stock. Note: This measure is loaded from an external system. (Read only)
End of Store Promotion Factor (expanded)	The expanded version of End of Store Promotion Factor will display the actual value used in the calculations. This version will display a factor of 1 for the days within the promotion period prior to the ramp down and will then show the designated End of Promotion Factor values as it approaches the end of the promotion. A factor of 1 will be displayed after the promotion has ended.
Projected Stock Out	Projected Stock Out is calculated based on forecasted demand and projected inventory. Note: This measure is information only. It is used in the High Projected Out of Stock Alert.

Measure Label	Description
Projected Stock Out – What if	Projected Stock Out – What if will initially display the value calculated in the previous AIP Batch run. If any changes are made to SRP parameters and the user selects ‘What If – Unconstrained’ or ‘What If – Constrained’ from the ‘What If’ button on the menu bar, this measure will be updated with the newly calculated projected stock out for the SKU/Store. (Read only)
Store Available To Plan Receipt	The Store Available To Plan Receipt (ATP) indicates the days on which a store may plan a receipt based on the store’s release schedule. A checkmark in a box indicates a receipt may be planned on that day. (Read only)
Store AWS Factor	The AWS Factor allows SRP users to provide a numeric factor to be multiplied against the average weekly sales (AWS) to determine replenishment boundaries (safety stock, receipt point and receive up to level) for the Factor AWS replenishment method. Any positive number is valid. Special Values: -1 (Use Previous) -2 (Use Default) Example: To calculate a safety stock that is 50% of the average weekly sales, the user would enter an AWS Factor of .5.
Store AWS Factor (expanded)	The expanded version of Store AWS Factor will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered. (Read only)

Measure Label	Description
Store Boundary Stock	The Boundary Stock identifier allows SRP users to select the stock level to use in calculating the Store Receipt Point and Store Receive Up to Level. This stock level is a combination of Safety Stock, Presentation Stock and/or Promotional Presentation Stock based on the identifiers listed below. If the identifier contains “vs”, the greater value will be used. This parameter affects all replenishment methods. The user selects the boundary stock identifier from the following picklist options: ▪ SS vs PS + PPS ▪ SS vs PS ▪ SS vs PPS ▪ SS + PS + PPS ▪ SS + PS ▪ SS + PPS ▪ SS Where, SS = Safety Stock PS = Presentation Stock PPS = Promotional Presentation Stock The picklist default is SS vs PS + PPS. Example: Selecting SS vs PS will add the greater of SS or PS to the calculated Store Receipt Point and Store Receive Up to Level values. Selecting SS + PS will add the total of SS and PS to the calculated Store Receipt Point and Store Receive Up to Level values.
Store Boundary Stock (expanded)	The expanded version of Store Boundary Stock will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered. (Read only)
Store Customer Orders	Store Customer orders (CO) are orders placed by customers at a store for a specific quantity of a SKU to be picked up on a specific delivery date. Customer orders are treated as additional demand on top of normal forecasted demand. Note: Customer Orders are loaded to SRP from an external system. (Read only)
Store Customer Orders Over Review Time	Store Customer Orders Over Review Time represents the customer Orders that must be accounted for when calculating the ideal receipt quantity on an ATP day. Customer Orders are summed from the day after the beginning of the review period through the day before the end of the review period. Store Customer Orders Over Review Time is only calculated on Available to Plan receipt days. (Read only)
Store Demand Forecast	The Store Demand Forecast is the forecast of the store’s future sales. Note: Demand Forecast is loaded from an external forecasting system. (Read only)

Measure Label	Description
Store Demo Stock	Amount of stock that is used as demonstration product, but is still available to sell. Demo Stock is added to the RP and RUTL levels for each day. Any positive number, including zero, is valid. Special Values: -1 (Use Previous) -2 (Use Default)
Store Demo Stock (expanded)	The expanded version of Store Demo Stock will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered. (Read only)
Store Expected Receipts	Store Expected Receipts (ER) are orders that have already been executed and therefore need to be considered when planning future orders for a store. Store Expected Receipts is the sum of in-transits and on orders. Note: In-transits and on orders s are loaded to SRP from an external system. (Read only)
Store Forecast Demand Over Review Time	The Store Forecast Demand Over Review Time is calculated as the sum of the forecasted demand from the current day through the next receipt day. Store Forecast Demand Over Review Time is only calculated on Available to Plan receipt days. (Read only)
Store Increment Percent	The Increment Percent acts as a multiplier for minimum and maximum stock that is designed to handle temporary fluctuation in demand for items using the Min/Max Replenishment Method. An increment percentage factor can be used to temporarily increase or decrease targeted stocking levels without altering the established MIN and MAX values. Any positive number, including zero, is valid. Special Values: -1 (Use Previous) -2 (Use Default) Example: To use 120% of the Min and Max Stock, the user would enter an Increment Percent of 1.2.
Store Increment Percent (expanded)	The expanded version of Store Increment Percent will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered. (Read only)

Measure Label	Description
Store Inventory Selling Days	The Inventory Selling Days parameter is used to specify the number of days of forecast quantity to be used when calculating the Receive up to Level (RUTL) with the Hybrid, Dynamic, Poisson and Loaded SS Dynamic Replenishment Methods. The RUTL calculation will use the forecast demand over the greater of Inventory Selling Days and Review Time. Inventory Selling Days can be used to avoid producing very small frequent orders. Any positive integer, including zero, is valid. Special Values: -1 (Use Previous) -2 (Use Default) Example: To ensure an order will contain at least 14 days of supply, 14 would be entered as the number of Inventory Selling Days.
Store Inventory Selling Days (expanded)	The expanded version of Store Inventory Selling Days will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered. (Read only)
Store Max Safety Stock Days	The Max Safety Stock Days parameter is used to specify the maximum number of days of cover to be kept on hand as safety stock. If the user enters both Max Safety Stock Days and Max Safety Stock Units, the maximum safety stock boundary will use the larger of demand over max safety stock days and max safety stock units. Any positive integer, including zero, is valid. Special Values: -1 (Use Previous) -2 (Use Default) -3 (Unbounded) Example: To ensure the maximum safety stock will contain at least 14 days of supply, 14 would be entered in Max Safety Stock Days. If Max Safety Stock Units is greater than 14 days of supply, max units would be used as the maximum safety stock, otherwise maximum safety stock would be the number of units required to cover 14 days of demand.
Store Max Safety Stock Days (expanded)	The expanded version of Store Max Safety Stock Days will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered. (Read only)

Measure Label	Description
Store Max Safety Stock Units	The Max Safety Stock Units parameter is used to specify the maximum amount of inventory to be kept on hand as safety stock. If the user enters both Max Safety Stock Days and Max Safety Stock Units, the maximum safety stock boundary will use the larger of demand over max safety stock days and max safety stock units. Any positive number, including zero, is valid. Special Values: -1 (Use Previous) -2 (Use Default) -3 (Unbounded) Example: To ensure the maximum safety stock will contain at least 14 days of supply, 14 would be entered in Max Safety Stock Days. If Max Safety Stock Units is greater than 14 days of supply, max units would be used as the maximum safety stock, otherwise maximum safety stock would be the number of units required to cover 14 days of demand
Store Max Safety Stock Units (expanded)	The expanded version of Store Max Safety Stock Units will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered. (Read only)
Store Max Stock	Max Stock is only used in the Min/Max Replenishment Method. It represents the maximum stock level in units that are desired on hand to satisfy demand. The receipt plan quantity is calculated to bring Net Inventory up to MAX Stock. Any positive number, including zero, is valid. Special Values: -1 (Use Previous) -2 (Use Default) -3 (Unbounded)
Store Max Stock (expanded)	The expanded version of Store Max Stock will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered. (Read only)
Store Max Time Supply Days	Max Time Supply Days is only used in the Time Supply Replenishment Method. It represents maximum stock level in terms of number of days cover that that are desired on hand to satisfy demand. The receipt plan quantity is calculated to bring Net Inventory up to Maximum Time Supply Days of cover. Any positive integer, including zero, is valid. Special Values: -1 (Use Previous) -2 (Use Default) Example: To ensure an order will bring the inventory level up to 14 days of supply, 14 would be entered in Max Time Supply Days.
Store Max Time Supply Days (expanded)	The expanded version of Store Max Time Supply Days will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered. (Read only)

Measure Label	Description
Store Min Safety Stock Days	The Min Safety Stock Days parameter is used to specify the minimum number of days of cover to be kept on hand as safety stock. If the user enters both Min Safety Stock Days and Min Safety Stock Units, the minimum safety stock boundary will use the larger of demand over min safety stock days and min safety stock units. Any positive integer, including zero, is valid. Special Values: -1 (Use Previous) -2 (Use Default) Example: To ensure the minimum safety stock will contain at least 7 days of supply, 7 would be entered in Min Safety Stock Days. If Min Safety Stock Units is greater than 7 days of supply, min units would be used as the minimum safety stock, otherwise minimum safety stock would be the number of units required to cover 7 days of demand.
Store Min Safety Stock Days (expanded)	The expanded version of Store Min Safety Stock Days will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered. (Read only)
Store Min Safety Stock Units	The Min Safety Stock Units parameter is used to specify the minimum amount of inventory to be kept on hand as safety stock. If the user enters both Min Safety Stock Days and Min Safety Stock Units, the minimum safety stock boundary will use the larger of demand over min safety stock days and min safety stock units. Any positive number, including zero, is valid. Special Values: -1 (Use Previous) -2 (Use Default) Example: To ensure the minimum safety stock will contain at least 7 days of supply, 7 would be entered in Min Safety Stock Days. If Min Safety Stock Units is greater than 7 days of supply, min units would be used as the minimum safety stock, otherwise minimum safety stock would be the number of units required to cover 7 days of demand.
Store Min Safety Stock Units (expanded)	The expanded version of Store Min Safety Stock Units will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered. (Read only)
Store Min Stock	Min Stock is only used in the Min/Max Replenishment Method. It represents the minimum stock level in units that are desired on hand to satisfy demand. Min Stock is used in determining the inventory level at which a replenishment is triggered. Any positive number, including zero, is valid. Special Values: -1 (Use Previous) -2 (Use Default)
Store Min Stock (expanded)	The expanded version of Store Min Stock will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered. (Read only)

Measure Label	Description
Store Min Time Supply Days	Min Time Supply Days is only used in the Time Supply and Hybrid Replenishment Method. It represents minimum stock level in terms of number of days cover that that are desired on hand to satisfy demand. Min Time Supply Days of cover is used in both safety stock and receipt point calculations. Any positive integer, including zero, is valid. Special Values: -1 (Use Previous) -2 (Use Default) Example: To ensure a minimum inventory level that will cover 7 days of supply, 7 would be entered in Min Time Supply Days.
Store Min Time Supply Days (expanded)	The expanded version of Store Min Time Supply Days will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered. (Read only)
Store MSQ Constraint Indicator (expanded)	The expanded version of Store MSQ Constraint Indicator displays the actual value used in calculations. This represents the merge of the global default, default and exception level versions of Store MSQ Constraint Indicator. If the indicator is "On", MSQ will be applied as a constraint during ordering decisions.
Store Net Inventory	Store Net Inventory (NI) is calculated in batch AIP and is a prediction of the inventory position at the end of review time. It represents what inventory will be available to meet demand over the period. The NI calculation is based on the Projected Inventory position at the beginning of the period, then considering the impact of expected receipts and expected spoilage (ER & ES) over the review time. Store Net Inventory is only calculated on Available to Plan receipt days, and is used as the point at which SRP will generate a planned receipt. (Read only)
Store Net Inventory – What if	Store Net Inventory – What if will initially display the NI calculated in the previous AIP Batch run. If any changes are made to SRP parameters and the user selects 'What If – Unconstrained' or 'What If – Constrained' from the 'What If' button on the menu bar, this measure will be updated with the newly calculated net inventory for the SKU/Store. Store Net Inventory – What if is only calculated on Available to Plan receipt days. (Read only)
Store Ordering Pack Size	The Store Ordering Pack Size represents the primary pack size to be used when ordering a SKU for a store (either from a warehouse or from a supplier). Note: Store Ordering Pack Size is loaded from Data Management online (DMo). (Read only)

Measure Label	Description
Store Percent of Pallet	Percent of pallet is used to determine if the Ideal Receipt Quantity for replenishment should be rounded to a full pallet. It represents the percentage threshold that case demand must exceed in order for pallet rounding to occur. Valid values are 0 through 1. Special Values: -1 (Use Previous) -2 (Use Default) Example: If an SRP user wants to round an order up to a pallet if the case demand is greater than 75 percent of a pallet, the user would enter .75 in Percent of Pallet.
Store Percent of Pallet (expanded)	The expanded version of Store Percent of Pallet will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered. (Read only)
Store Projected Inventory	Store Projected Inventory (PI) is calculated in AIP batch and represents a projection of the opening inventory position for any day in the planning horizon at a specific store. None of that day's activities (either receipts or demand) are reflected in PI, and so it is often referred to as a "beginning of day" position. PI on a given day is calculated as the PI of the previous day plus the net impact of all demand and replenishments on the previous day. Previous day demand is consists of forecasted demand plus any customer orders (CO) on that day. Previous day replenishments consist of Expected and Planned Receipts. (Read only)
Store Projected Inventory – What if	Store Projected Inventory – What if will initially display the PI calculated in the previous AIP Batch run. If any changes are made to SRP parameters and the user selects 'What If – Unconstrained' or 'What If – Constrained' from the 'What If' button on the menu bar, this measure will be updated with the newly calculated projected inventory for the SKU/Store. (Read only)
Store Promotion Presentation Stock	The Store Promotion Presentation Stock represents the End of Store Promotion Factor applied to the Base Store Promotion Presentation Stock. If the Store Promotion Presentation Stock Override Flag is turned on, this becomes equal to "0".
Store Promotion Presentation Stock Override Flag	The Store Promotion Presentation Stock Override Flag indicates what value should be used for Store Promotion Presentation Stock. When the override flag is turned on ("TRUE"), the Store Promotion Presentation Stock equals "0".
Store Promotion Presentation Stock Override Flag (expanded)	The expanded version of Store Promotion Presentation Stock Override Flag will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered.

Measure Label	Description
Store Receipt Plan	The Store Receipt Plan represents SRP's recommendations for ordering based on demand, allocation boundaries and available inventory. The Receipt Plan is final result calculations in AIP Batch including adjustments made to Ideal Receipt Quantity based on rounding and constraints made to the unconstrained receipt plan based on inventory available at the source. (Read only)
Store Receipt Plan - What if	Store Receipt Plan– What if will initially display the Receipt Plan calculated in the previous AIP Batch run. If any changes are made to SRP parameters and the user selects 'What If – Unconstrained' or 'What If – Constrained' from the 'What If' button on the menu bar, this measure will be updated with the newly calculated Receipt Plan for the SKU/Store. If 'What If – Unconstrained' is selected the 'what if receipt plan' will represent the calculated plan after replenishment. It will not consider whether or not the required inventory to meet the plan is available at the source. If 'What If – Constrained' is selected the 'what if receipt plan' will represent the calculated plan after replenishment and shortfall reconciliation. It will not consider substitution or SPQ availability. (Read only)
Store Receipt Point	The Store Receipt Point (RP) represents the inventory level below which an order should be triggered. Receipt point is calculated differently based on the selected Replenishment Method. Store Receipt Point is only calculated on Available to Plan receipt days. (Read only)
Store Receipt Point – What if	Store Receipt Point – What if will initially display the receipt point (RP) calculated in the previous AIP Batch run. If any changes are made to the RP parameters and the user selects 'Calculate', the newly calculated receipt point will be displayed. If the user selects 'What If – Unconstrained' or 'What If – Constrained' from the 'What If' button on the menu bar, the receipt plan will be updated using the newly calculated receipt point and any other parameter changes for the SKU/Store. Store Receipt Point – What if is only calculated on Available to Plan receipt days. (Read only)
Store Receive Up to Level	The Receive Up To level (RUTL) denotes the target level of inventory when generating an order. Receive Up To Level is calculated differently based on the selected Replenishment Method. Store Receive Up to Level is only calculated on Available to Plan receipt days. (Read only)

Measure Label	Description
Store Receive Up to Level – What if	Store Receive Up to Level – What if will initially display the Receive Up To Level (RUTL) calculated in the previous AIP batch run. If any changes are made to the RUTL parameters and the user selects 'Calculate', the newly calculated receive up to level will be displayed. If the user selects 'What If – Unconstrained' or 'What If – Constrained' from the 'What If' button on the menu bar, the receipt plan will be updated using the newly calculated receive up to level and any other parameter changes for the SKU/Store. Store Receive Up to Level – What if is only calculated on Available to Plan receipt days. (Read only)
Store Reconciled Orders	The Store Reconciled Orders is an indicator informing users which indicates which orders have been reconciled. (Read only)
Store Reconciliation Adjustment	The Store Reconciliation Adjustment represents the difference between the Unconstrained Receipt Plan and the Store Receipt Plan due to inventory constraints, inventory availability at the source location. (Read only)
Store Release Schedule	The Store Release Schedule is an integer representing the lead time from a source location to store for a SKU. The release schedule is calculated in Data Management (DM) based on lead time and order cycle. (Read only)
Store Repl Method	The choice of Replenishment Method determines the calculations that will be used in generating a store replenishment method. The user selects the Replenishment Method from the following picklist options: ▪ Min/Max ▪ Time Supply ▪ Dynamic ▪ Hybrid ▪ No Replenishment ▪ Poisson Replenishment ▪ Loaded SS Dynamic ▪ Sales Week Range ▪ Factor AWS The picklist default is No Replenishment
Store Repl Method (expanded)	The expanded version of Store Repl Method will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered. (Read only)

Measure Label	Description
Store Rounding Method	The Rounding Method is used when pack rounding the ideal receipt quantity (IRQ). The user selects the Rounding Method value from the following picklist options: ▪ Unspecified ▪ Order Pack ▪ Normal Unspecified defaults to 'Normal'.
Store Rounding Method (expanded)	The expanded version of Store Rounding Method will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered. (Read only)
Store Rounding Threshold	The Rounding Threshold represents the portion of a pack above which the replenishment plan is rounded up and below which it is rounded down. Valid values are 0 through 1. Special Values: -1 (Use Previous) -2 (Use Default) Example: If an SRP user wants to round an order up to a pack if the demand is greater than 25 percent of a pack, the user would enter .25 in Rounding Threshold.
Store Rounding Threshold (expanded)	The expanded version of Store Rounding Threshold will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered. (Read only)
Store Safety Stock	Store Safety Stock (SS) is inventory held at a location to mitigate the risks of stock outs caused by variability in forecasted demand. Safety stock is calculated differently based on the selected Replenishment Method. All replenishment methods allow the safety stock to be bound by minimum and maximum values. Store Safety Stock is only calculated on Available to Plan receipt days. (Read only)
Store Safety Stock – What if	Store Safety Stock – What if will initially display the safety stock (SS) calculated in the previous AIP Batch run. If any changes are made to the SS parameters and the user selects 'Calculate', the newly calculated safety stock will be displayed. If the user selects 'What If – Unconstrained' or 'What If – Constrained' from the 'What If' button on the menu bar, the receipt plan will be updated using the newly calculated safety stock and any other parameter changes for the SKU/Store. Store Safety Stock – What if is only calculated on Available to Plan receipt days. (Read only)

Measure Label	Description
Store Safety Stock Level Factor	The Safety Stock Level Factor represents the amount of additional safety stock to carry in anticipation of unpredictable events (for instance, weather changes) or to provide additional safety stock during a special promotion or event. This will provide a temporary lift in the Receipt Point (RP) and Receive Up To Level (RUTL) values. The Safety Stock Level Factor is used in Time Supply, Hybrid, Poisson, Dynamic and Loaded SS Dynamic Replenishment Methods. Example: To increase safety stock by 25 units, the user would enter a Safety Stock Level Factor of 25. Negative values may also be entered to decrease the safety stock level.
Store Safety Stock Level Factor (expanded)	The expanded version of Store Safety Stock Level Factor will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered. (Read only)
Store Service Level	The Service Level is used in the safety stock calculations for the Dynamic and Poisson replenishment methods. It is defined as the percentage of demand that the stock should be able to meet demand. Valid values are 0 through 1. Special Values: -1 (Use Previous) -2 (Use Default) Example: If an SRP user wants to carry enough safety stock to maintain a 90% customer service level, the user would enter .90 in Service Level.
Store Service Level (expanded)	The expanded version of Store Service Level will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered. (Read only)
Store Shelf Capacity	Shelf capacity is the amount of stock to fill a shelf to the desired maximum level. If the Shelf Capacity Flag is set to 'Yes', the shelf capacity is used to cap the receipt point and receive up to level. Any positive number, including zero, is valid. Special Values: -1 (Use Previous) -2 (Use Default)
Store Shelf Capacity (expanded)	The expanded version of Store Shelf Capacity will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered. (Read only)

Measure Label	Description
Store Shelf Capacity Flag	The Shelf Capacity Flag is used to determine if the receipt point and receive up to level should be capped by the shelf capacity. The user selects the Shelf Capacity Flag value from the following picklist options: ▪ Yes ▪ No ▪ Default Example: Selecting 'Yes' will cause SRP to use shelf capacity to cap receipt point and receive up to level. Selecting 'No' or 'Default' indicates SRP will not use shelf capacity to cap receipt point and receive up to level.
Store Shelf Capacity Flag (expanded)	The expanded version of Store Shelf Capacity Flag will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered. (Read only)
Store Source Label	The Store Source Label identifies the source from which this store receives inventory. (Read only)
Store Time Supply Horizon	The Time Supply Horizon parameter is used to specify days of forecast in order to calculate a rate of sale. If a time supply horizon is specified, the rate of sale is used instead of the actual forecast when calculating demand over the time supply days for inventory target level calculations for the Time Supply Replenishment Method. Any positive integer, including zero, is valid. Special Values: -1 (Use Previous) -2 (Use Default) Example: To calculate a Rate of Sale (ROS) over a one week period, enter a value of 7 in Time Supply Horizon. The (ROS) is then calculated by summing the forecasted sales over the 7 days and dividing that number by 7.
Store Time Supply Horizon (expanded)	The expanded version of Store Time Supply Horizon will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered. (Read only)
Store Weekly Sales Max	Maximum stock boundary for the Factor AWS, Sales Date Range, and Loaded SS Dynamic replenishment methods. Any positive number, including zero, is valid. Special Values: -1 (Use Previous) -2 (Use Default) -3 (Unbounded)

Measure Label	Description
Store Weekly Sales Max (expanded)	The expanded version of Store Weekly Sales Max will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered. (Read only)
Store Weekly Sales Min	Minimum stock boundary for the Factor AWS, Sales Date Range, and Loaded SS Dynamic replenishment methods. Any positive number, including zero, is valid. Special Values: -1 (Use Previous) -2 (Use Default)
Store Weekly Sales Min (expanded)	The expanded version of Store Weekly Sales Min will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered. (Read only)
User Specified Store Presentation Stock	User Specified Store Presentation Stock is the minimum amount of stock in units desired to have on hand for display/sales purposes. User Specified Store Presentation Stock may be taken into consideration when calculating the Receipt Point and Receive up to Level, depending on the Boundary Stock selected. Any positive number, including zero, is valid. Special Values: -1 (Use Previous) -2 (Use Default)
User Specified Store Presentation Stock (expanded)	The expanded version of User Specified Store Presentation Stock (expanded) will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered. (Read only)

Hidden Workbook Measures

The following measures are hidden when using the default template. They can be displayed and maintained by using the Insert measure function of RPAS.

Measure Label	Description
Active SKU CAP (Units) (Expanded)	SKU Cap (value in units) is used in store replenishment calculations. During replenishment calculations, this is the maximum boundary for inventory at the store.
Aggregated Store Ads	Aggregated Store Ads indicates the presence of any active ads within the SKU Group/Week level. Aggregated Store Ads is true if at least one ad exists over the week for this SKU Group.
Cases Per Pallet	Cases Per Pallet reflects the number of cases on a pallet. Note: Cases Per Pallet is loaded from Data Management online (DMo). (Read only)

Measure Label	Description
Daily Sales	Daily Sales represents the daily sales for a SKU/Store/Day. Note: This measure is loaded from an external system for use in calculating SRP alerts. (Read only)
Store Acceptable Loss	Store Acceptable Loss represents the percentage of a case that is acceptable to lose from spoilage in order to prevent stock outs. This measure is used when rounding ideal receipt quantities. The user can enter a value in either Store Acceptable Loss or Store Spoilage Threshold in this worksheet. If a user edits Store Acceptable Loss, - Store Spoilage Threshold will be disabled for update - Store Spoilage Threshold will be calculated as 1 minus Store Acceptable Loss Store Acceptable Loss will be updated in the database with the calculated value (If commit is selected) Valid values are 0 through 1. Special Values: -1 (Use Previous) -2 (Use Default) Example: If it is acceptable to lose 25% of a case from spoilage, the user would enter a Store Acceptable Loss of .25. In this case, spoilage threshold would be calculated as .75, but only acceptable loss would be updated in the database.
Store Acceptable Loss (expanded)	The expanded version of Store Acceptable Loss will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered. (Read only)
Store Ads Grand Opening	Store Ads Grand Opening indicates grand opening ads exist for this SKU/Store/Day. This measure can be aggregated to provide information regarding the number of locations that are on Ad. Note: This measure is loaded from an external system. (Read only)
Store Ads Inserts	Store Ads Inserts indicates inserts ads exist for this SKU/Store/Day. This measure can be aggregated to provide information regarding the number of locations that are on Ad. Note: This measure is loaded from an external system. (Read only)
Store Ads Others	Store Ads Others indicates other miscellaneous ads exist for this SKU/Store/Day. This measure can be aggregated to provide information regarding the number of locations that are on Ad. Note: This measure is loaded from an external system. (Read only)

Measure Label	Description
Store Ads Run on Press	Store Ads Run on Press indicates run on press ads exist for this SKU/Store/Day. This measure can be aggregated to provide information regarding the number of locations that are on Ad. Note: This measure is loaded from an external system. (Read only)
Store Available Space	Store Avail Space represents the remaining space available under the SKU Cap after considering Store Inventory and Expected Receipts over the appropriate time period(s).
Store Avg Rate of Sale	Store Avg Rate of Sale represents an item's average daily rate of sale at a store. Note: This measure is loaded from an external system at the SKU/Store level and spread to the SKU/Store/Day level across the planning horizon. (Read only)
Store Capped Difference	The Store Capped Difference is equal to Non-Capped URP – URP on any ATP day.
Store Demand on Source	The Store Demand on Source is equal to the URP time-shifted backwards based on the lead-time on the receipt day of the URP into the store.
Store Expected Spoilage	Expected Spoilage refers to a quantity of a SKU at a store whose product life expires and therefore becomes un-sellable at the end of a day. Expired quantities can not be used for any sales after the day they expire. Expected spoilage is only calculated when the global Inventory Aging Flag is set to true, the Product Life of the SKU is greater than zero and the Product Life of the SKU is less than or equal to the Aging Threshold. The calculation is based on the inventory position, demand, expected receipts and product life. The user can specify an expected write-off quantity which will override the expected spoilage if the write-off quantity is greater than the calculated value. (Read only)
Store Expected Write-off	Store Expected Write-off represents the quantity of stock expected to be thrown out for any reason (spoilage, breakage, etc.) on a given day. Expected Write-offs override calculated expected spoilage. Note: This measure is loaded from an external system. (Read only)
Store Intransits	Store Intransits represents Inventory in transit from warehouses and suppliers to store. Note: This measure is loaded from an external system. (Read only)
Store Known Demand	Store Known Demand is the quantity in units of confirmed demand that is known for any reason. Known demand is used in place of the forecast if the known demand is greater than the forecast. Note: This measure is loaded from an external system. (Read only)

Measure Label	Description
Store Loaded Safety Stock History	Store Loaded Safety Stock History maintains history of the Loaded safety stock measure. Note: This measure is loaded from an external system. (Read only)
Store Maximum Sellable Quantity	Store Maximum Sellable Quantity (MSQ) represents a level of inventory that can be sold within the life of a product. It is calculated as all forecast demand over the product life starting from the beginning of the review time. Customer orders over the review time (CORT), an additional non-forecast-able source of demand, are then added. Store Maximum Sellable Quantity is only calculated on Available to Plan receipt days. As MSQ is dependent upon Product Life (PL), where Product Life is deemed to be not relevant for a SKU, the MSQ is considered infinite (Unbounded). (Read only)
Store Minimum Sales Stock	Store Minimum Sales Stock (MSS) represents a level of inventory required to meet demand. This is calculated as forecast demand over the review time. Customer orders over the review time (CORT). For those replenishment methods where forecasted demand is not used, demand in the MSS calculation is replaced with calculated Safety Stock. Store Minimum Sales Stock is only calculated on Available to Plan receipt days. If a shelf capacity constraint exists (Shelf Capacity Flag is set to true) Store Minimum Sales Stock may not exceed the level required to fill the shelf to capacity and meet CORT. (Read only)
Store Non-Capped Demand on Source	The Store Non-Capped Demand on Source is equal to the Non-Capped URP time-shifted backwards based on the lead-time on the receipt day of the URP into the store.
Store Non-Capped URP	Store Non-Capped URP represents the theoretical URP at the SKU/Store/day level, which would have been calculated if the SKU was not capped at all across time.
Store Numeric In Scope Indicator	Store Numeric In Scope Indicator is used in SRP alert processing to determine the alerting store ratio. It represents the number of stores for a SKU that are 'in-scope' (stores which fall between on supply and off supply) during the alert horizon. (Read only)
Store On Orders	Store On Orders are fixed orders currently being processed for delivery to store either from warehouses or directly from suppliers Note: This measure is loaded from an external system. (Read only)
Store Placed CRP	Store Placed CRPs are planned orders generated within the placement lead-time. They represent receipt plans previously generated but not released. These CRPs will not be deleted or changed within the placement lead-time, but will be saved for release on the future release date. (Read only)

Measure Label	Description
Store Placed Orders	Store Placed Orders indicates which orders have been placed. Once an order is placed, it cannot be changed within the store placement lead-time, unless a USA is raised. Placed orders can be generated from a User Specified Allocation (USA) or during the nightly batch process when the store has a longer placement lead time than release schedule. (Read only)
Store Placement Schedule	The Store Placement Schedule defines the time required by the supplier to plan for an order and the lead-time to get the order to the store. Once an order is placed, it cannot be changed within the store placement lead-time, unless a USA is raised. The Store Placement Schedule must be a valid release date based on the Store Release Schedule greater than the release schedule. Note: The Store Placement Schedule is calculated in Data Management online (DMo). (Read only)
Store Product Life	Store Product Life represents the number of days from the time a product arrives at the store until it spoils. Any positive integer, including zero, is valid. Special Values: -1 (Use Previous)
Store Recommended Coupled Flag	The Store Recommended Coupled Flag coupled flag is an information only flag to indicate a placement lead-time is recommended for this SKU. The coupled flag is not used in any calculations and does not determine that the placement lead-time is used. TRUE means recommended coupled orders. FALSE means recommended decoupled orders. Note: This measure is loaded from Data Management online (DMo). (Read only)
Store Review Time	Store Review Time is a calculated measure indicating the number of days until the next delivery. Store Review Time is only calculated on Available to Plan receipt days. (Read only)
Store Spoilage Threshold	Spoilage threshold is used as a pack rounding constraint. While Acceptable Loss is the value maintained in the database, SRP users can change either Acceptable Loss or Spoilage Threshold. If a user edits Default Spoilage Threshold, Acceptable Loss will be disabled for update and Acceptable Loss is calculated as 1 minus Spoilage Threshold. Valid values are 0 through 1. Special Values: -1 (Use Previous) -2 (Use Default) Example: To maintain at least 75% of a case without spoilages, the user would enter a Store Spoilage Threshold of .75. In this case, acceptable loss would be calculated as .25 and acceptable loss would be updated in the database.

Measure Label	Description
Store Spoilage Threshold (expanded)	The expanded version of Store Spoilage Threshold will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered. (Read only)
Supplier Compliance Safety Stock Uplift	Supplier Compliance Safety Stock Uplift represents additional safety stock units added to the calculated safety stock. The Supplier Compliance Safety Stock Uplift is calculated as a number of days of demand going forward from the larger of review time or number of inventory selling days. Any positive number, including zero, is valid. Special Values: -1 (Use Previous) -2 (Use Default)
Store USA Over Review Time	Store USA Over Review Time (USART) is the sum of User Specified Allocations over the review time. Store USA Over Review Time is only displayed on Available to Plan receipt days. (Read only)
Store USA Over Review Time Type	The Store USA Over Review Time Type measure indicates the allocation combination type that is used when regarding the USART quantity as a whole. The first populated USA type in the review time is used as the USART type. Store USA Over Review Time Type Time is only displayed on Available to Plan receipt days. (Read only)
Store User Specified Allocation	Store User Specified Allocations (USA) are allocations that are defined by the user and accounted for in projected inventory. USAs are maintained in the USA workbooks. (Read only)

SRP Replenishment Plan (SKU/Store/Week) Worksheet

SRP Replenishment Plan (SKU/Store/Week) Worksheet

The loaded and calculated measures are read only. Parameter values at the SKU/Store/Week level may be maintained. Expanded measures are read only.

The following measures appear automatically when using the default template.

Measure Label	Description
Actual Weekly Sales	Actual Weekly Sales is used in Sales Week Range and Factor AWS replenishment methods. It represents the actual sales by week for a SKU/Store. As a default, SRP maintains the last 52 weeks of history (purge age is set to 371). This ensures that the oldest week of history is automatically dropped as each new week of sales history is added. Note: Actual Weekly Sales is loaded to SRP from an external system. (Read only)
Store Roll Weeks	The Roll Weeks parameter indicates whether SRP logic should automatically roll the start and end date range settings forward one week or not. Roll weeks is used in the Factor AWS Sales Date Range Replenishment Methods. The user selects the Roll Weeks value from the following picklist options: ▪ Yes ▪ No ▪ Default Example: Selecting 'Yes' will cause the start and end date to roll forward one week, allowing the user to keep the weekly historical sales at the same relative distance in the past. Selecting 'No' will not move the start and end date forward allowing the user to use the same weekly historical sales as the system moves forward in time.
Store Roll Weeks (expanded)	The expanded version of Store Roll Weeks will display the actual value used in the calculations. This is the merge exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered. (Read only)

SRP Replenishment Plan (SKU/Store) Worksheet

Location	Product	
S303 - MISHAWAKA IN	100035008 - CALCULATC	100037020 - PROJECTOR
Like SKU		
Like SKU End Date		
Off-Supply Effective Date	12/29/2007	12/29/2007
On-Supply Effective Date	12/29/2003	12/29/2003
Projected Stock Out	875.00	1000.00
Projected Stock Out - What If	1600.00	1600.00
RDF Detail Alert Count	0	0
RDF Detail Alert Mask	☒	☒
SRP RDF Detailed Alert	☐	☐
Store Current Inventory	0.00	0.00
Store End Date Range		
Store End Date Range (expanded)	7/15/2008	7/15/2008
Store Repl Subtype Code		
Store Repl Type Code		
Store Start Date Range		
Store Start Date Range (expanded)	7/15/2008	7/15/2008
Use Like SKU	☐	☐

Measure

SRP Replenishment Plan (SKU/Store) Worksheet

The following measures appear automatically when using the default template. The loaded and calculated measures are read only. Parameter values at the SKU/Store level may be maintained. Expanded measures are read only.

Measure Label	Description
Like SKU	Like SKU allows the SRP user to select a similar SKU to obtain sales history from for new SKUs or SKUs with scant historical data. The new SKU will use the Like SKUs history until the Like SKU End Date when the new SKU has built up stable sales history. The Like SKU's sales history is used in the RP and RUTL boundaries for a new SKU using the Sales Week Range or Factor AWS replenishment method. Valid values are any SKU within the same domain as the new SKU.
Like SKU End Date	The Like SKU End Date parameter allows SRP users to select the date that should be used as the ending point for using the Like SKUs sales history in calculations for the "Sales Date Range" and "Factor AWS" replenishment methods. A pop-up calendar can be used to select the desired end date.
Off-Supply Effective Date	The Off-Supply Effective Date represents the date a store should stop receiving the product. Note: The Off-Supply Effective Date is loaded from Data Management online (DMo). (Read only)

Measure Label	Description
On-Supply Effective Date	The On-Supply Effective Date represents the date a store should begin receiving the product. Note: The On-Supply Effective Date is loaded from Data Management online (DMo). (Read only)
Projected Stock Out	Projected Stock Out is calculated based on forecasted demand and projected inventory.
Projected Stock Out – What if	Projected Stock Out – What if will initially display the value calculated in the previous AIP Batch run. If any changes are made to SRP parameters and the user selects ‘What If – Unconstrained’ or ‘What If – Constrained’ from the ‘What If’ button on the menu bar, this measure will be updated with the newly calculated projected stock out for the SKU/Store. (Read only)
RDF Detail Alert Count	The RDF Detail Alert Count represents the number of alert hits from a forecasting system for this SKU/Store. This allows the SRP User to consider if action needs to be taken in the forecasting system to correct a problem prior to making changes to any SRP parameters. Note: The RDF Detail Alert Count is loaded from an external system. (Read only)
RDF Detail Alert Mask	The RDF Detail Alert Mask allows the user to start or stop generating the RDF alert based on dates. If the alert mask is false for the SKU/Store/Day, no alert will be generated. Valid values are True or False. The RDF Detail Alert Mask default is True.
SRP RDF Detailed Alert	The SRP RDF Detailed Alert indicates an RDF alert exists for this SKU/Store. (Read only)
Store Current Inventory	Store Current Inventory represents the store’s on hand position inventory position. Note: Current Inventory is loaded from an external system. Negative values are rejected by SRP and replaced with a zero. There is a contingency process in the event that the load from a store fails. It will provide SRP with a system generated current store inventory value for its replenishment calculations. The calculations starts with yesterdays projected inventory position and adds in the difference between actual sales and forecasted demand. (Read only)
Store End Date Range	The End Date Range parameter allows SRP users to select the date that should be used as the ending point for determining the historical sales data used by the “Sales Date Range” and “Factor AWS” replenishment methods. In the Sales Date Range method, the date range is the period over which sales history is summed. In the Factor AWS method, it is the time period over which average weekly sales is calculated. A pop-up calendar can be used to select the desired end date. Select a date less than or equal to the current date.

Measure Label	Description
Store End Date Range (expanded)	The expanded version of Store End Date Range will display the actual value used in the calculations. This is the merge exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered. (Read only)
Store Repl Subtype Code	Store Repl Subtype Code represents user defined replenishment subtype codes. These codes are display only and are not used in any calculations. Note: Store Repl Subtype Code is loaded from an external system. (Read only)
Store Repl Type Code	Store Repl Type Code represents user defined replenishment subtype codes. These codes are display only and are not used in any calculations. Note: Store Repl Type Code is loaded from an external system. (Read only)
Store Start Date Range	The Start Date Range parameter allows SRP users to select the date that should be used as the starting point for determining the historical sales data used by the “Sales Date Range” and “Factor AWS” replenishment methods. In the Sales Date Range method, the date range is the period over which sales history is summed. In the Factor AWS method, it is the time period over which average weekly sales is calculated. A pop-up calendar can be used to select the desired start date. Select a date less than or equal to the current date.
Store Start Date Range (expanded)	The expanded version of Store Start Date Range will display the actual value used in the calculations. This is the merge exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered. (Read only)
Use Like SKU	Use Like SKU indicates whether or not the Like SKU will be used to obtain sales history in the RP and RUTL boundary calculations when using the Sales Week Range or Factor AWS replenishment method. Valid values are True or False. The Use Like SKU default is False.

Hidden Workbook Measures

The following measures are hidden when using the default template. They can be displayed and maintained by using the Insert measure function of RPAS. Hidden measures may also be added to the template during configuration.

Measure Label	Description
Store Freshness Flag	The Freshness Flag is only used when the Inventory Aging Limit is set (indicating the SKU has a product life). When the Freshness Flag is "TRUE," SRP will ensure that a store replenishment plan is generated for at least the customer orders over Review Time (CORT) regardless of the inventory position. The user selects the Freshness Flag value from the following picklist options: ▪ On ▪ Off ▪ Default
Store Freshness Flag (expanded)	The expanded version of Store Freshness Flag will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered. (Read only)
Store Loaded Safety Stock	Store Loaded Safety Stock represents safety stock value used when using Loaded SS Dynamic replenishment method. Note: This measure is loaded from an external system. (Read only)
Store Supplier Compliance Safety Stock	The Supplier Compliance Safety Stock parameter represents a 'number of days of supply' additional safety stock to deal with supplier and supply chain compliance issues. The days covered begins with the latest of Review Time or Inventory Selling Days. The calculated Supplier Compliance Safety Stock Units is added on to the Safety Stock. Any positive number, including zero, is valid. Example: To add an addition 7 days of supply, 7 would be entered in Supplier Compliance Safety Stock.
Store Supplier Compliance Safety Stock (expanded)	The expanded version of Store Supplier Compliance Safety Stock will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered. (Read only)

SRP Replenishment Plan Parameters (Store) Worksheet

SRP Replenishment Plan Parameters (Store) Worksheet

The following measures are displayed automatically when using the default template. The loaded and calculated measures are read only. All measures are loaded and read only.

Measure Label	Description
Sister Store	A Sister Store allows the user to model a new store after a store with similar characteristics and anticipated similar sales. To do this, a "Sister Store" relationship is set up in RMS. Once this relationship is established, AIP will perform a one-time copy of all required replenishment settings and parameters from the sister store. AIP will perform a weekly copy of sales history from the sister store to a new store that is scheduled to open. It will continue to copy the sales history weekly up until the Store Opening Date.
Sister Store Parameters Flag	The Sister Store Parameters Flag Indicates that a sister store has had all store parameters copied from its sister store to itself. Note: This measure is loaded from Data Management online (DMo).
Store Open Date	Store Open Date is used in sister store copy; sales history from the sister store is copied to the new store until the new store reaches its opening date. Note: This measure is loaded from Data Management online (DMo).

SRP Replenishment Plan Parameters (SKU) Worksheet

SRP Replenishment Plan Parameters (SKU) Worksheet

Reconciliation Method is the only measure in this worksheet.

Measure Label	Description
Reconciliation Method	The Reconciliation Method is used to determine if reconciliation will occur on a day by day basis or over time. The user selects the Reconciliation Method value from the following picklist options: - Day-on-Day - Reconcile Over Time Example: Selecting 'Day-on-Day' will cause reconciliation from the source warehouse or supplier to occur for each day in the planning horizon. Day-on-Day reconciliation will ship the inventory out to the store or warehouse destination quickly, considering only those destination stores or warehouses where a shipment today would arrive on the available to plan (ATP) day. While this method may ship the inventory sooner than the 'Reconcile Over Time' method, stores or warehouses with ATP days later in the review period may receive less inventory than those with ATP days earlier in the review period. Selecting 'Reconcile Over Time' will cause reconciliation from the source warehouse or supplier to occur over each review period in the planning horizon. Reconcile Over Time allocation may cause some inventory to be retained at the source warehouse or supplier for shipment later in the review period. While this method may not ship the inventory as quickly as the 'Day-on-Day' method, all ATP days within the review period for all stores and warehouses will be considered equally in the inventory allocation.

WH Inventory Analysis (SKU Group/Warehouse/Day) Worksheet

	04/01/06	04/02/06	04/03/06	04/04/06
Store Projected DOS	0.00	0.00	0.00	0.00
Store Projected DOS - What if	0.00	0.00	0.00	0.00
Total Store Average Daily Sales	0.00	0.00	0.00	0.00
WH Expected Receipts	0.00	0.00	0.00	0.00
WH Projected DOS	0.00	0.00	0.00	0.00
WH Projected DOS - What if	0.00	0.00	0.00	0.00
WH Projected Inventory	0.00	0.00	0.00	0.00
WH Projected Inventory - What if	0.00	0.00	0.00	0.00
WH Total ARS	0.00	0.00	0.00	0.00

WH Inventory Analysis (SKU Group/Warehouse/Day) Worksheet

The following measures are displayed automatically when using the default template. This worksheet contains aggregate warehouse inventory information for review and inventory analysis purposes. All measures are read only.

Measure Label	Description
Store Projected DOS	Projected Days of Stock at the store indicates the total number of days of supply on-hand at stores on a given day for all stores sourced from a given warehouse. Store Projected DOS is calculated by summing the Store Projected Inventory measure for all stores sourced from a given warehouse and dividing that sum by the Total Store Avg Daily Sales.
Store Projected DOS – What if	Store Projected DOS – What if will initially display the projected days of stock calculated in the previous AIP Batch run. If any changes are made to SRP parameters and the user selects ‘What If – Unconstrained’ or ‘What If – Constrained’ from the ‘What If’ button on the menu bar, this measure will be updated with the newly calculated projected DOS for all stores sourced from a given warehouse.
Total Store Average Daily Sales	Total Store Average Daily Sales represents the sum of the daily Average Rate of Sale (ARS) for a given SKU on a given day for all the stores that are sourced from a given warehouse. Average Rate of Sale (ARS) is calculated by dividing the weekly ARS by 7. Note: Weekly ARS is an external load.
WH Expected Receipts	WH Expected Receipts represents the total warehouse expected receipts for the store’s source warehouse.
WH Projected DOS	WH Projected DOS at the warehouse indicates the total number of days of supply on-hand at the warehouse on a given day. WH Projected DOS is calculated in AIP Batch at SKUG/WH/Day level by taking the WH Projected Inventory divided by the WH Total Average Daily Sales.

Measure Label	Description
WH Projected DOS – What if	WH Projected DOS – What if will initially display the projected days of stock calculated in the previous AIP Batch run. If any changes are made to SRP parameters and the user selects ‘What If – Unconstrained’ or ‘What If – Constrained’ from the ‘What If’ button on the menu bar, this measure will be updated with the newly calculated projected DOS for the warehouse.
WH Projected Inventory	WH Projected Inventory (PI) represents a projection of the opening inventory position for any day in the planning horizon at the warehouse. None of that day’s activities (either receipts or demand) are reflected in PI, and so it is often referred to as a “beginning of day” position.
WH Projected Inventory – What if	WH Projected Inventory – What if will initially display the warehouse’s projected inventory calculated in the previous AIP batch run. If any changes are made to SRP parameters and the user selects ‘What If – Unconstrained’ or ‘What If – Constrained’ from the ‘What If’ button on the menu bar, this measure will be updated with the newly calculated projected inventory for the warehouse.
WH Total ARS	WH Total ARS represents the Total Store Avg Daily Sales and WH Independent ARS. It is calculated by adding the sum of the store ARS for all stores sourced from a given warehouse to the warehouse independent ARS.

Company Level Inventory Analysis Worksheet

This worksheet provides a company-wide view of inventory levels in the supply chain.

Product	04/01/06	04/08/06	04/15/06	04/22/06
100035008B - CALCULATOR,GRAPHING,SILVER				
Actual Weekly Sales	0.00	0.00	0.00	0.00
Actual Weeks Of Supply	0	0	0	0
Ad/Rollout Notes				
Aggregated Store Ads				
Aggregated Store Demo Stock	0.00	0.00	0.00	0.00
Company URP By Week	0.00	0.00	0.00	0.00
End of Week Inventory at Cross Docks	0.00	0.00	0.00	0.00
End of Week Inventory at Deconsolidation Centers	0.00	0.00	0.00	0.00
End of Week Inventory at RDCs	0.00	0.00	0.00	0.00
Expected Receipts from Vendors	0.00	0.00	0.00	0.00
Forecasted Receipts from Vendors	0.00	4000.00	0.00	0.00
Forecasted To Sell-Through %	0.00	0.00	0.00	0.00
Forecasted Weekly Sales	0.00	0.00	0.00	0.00
Forecasted Weeks Of Supply	0.00	0.00	0.00	0.00
Inventory Per Store	0.00	0.00	0.00	0.00

Company Level Inventory Analysis Worksheet

This worksheet contains the following read-only measures.

Measure Label	Description
Actual Weekly Sales	Actual Weekly Sales represents the sum of actual sales data from stores aggregated to the SKU Group/Week level.
Actual Weeks of Supply	Actual Total Weeks of Supply represents weeks of supply for all locations (stores and warehouses). It is calculated by dividing Saleable Inventory by Total Avg Weekly Sales.
Ad/Rollout Notes	SKU Ad/Rollout Notes contains notes related to a product ad or rollout.
Aggregated Store Ads	Aggregated Store Ads indicates the presence of any active ads within the SKU Group/Week level. Aggregated Store Ads is true if at least one ad exists over the week for this SKU Group.
Aggregated Store Demo Stock	Aggregated Store Demo Stock represents the total demo stock over the week for this SKU Group. It is calculated as the sum of demo stock across all stores on the last day of the week (Saturday).
Company URP by Week	Company URP by Week is the unconstrained receipt plan (URP) for a given SKU Group across the company for a given week. Unconstrained receipt plan (URP) is calculated as Store Receipt Plan (SKU/Store/Day) plus the Store Reconciliation Adjustment (SKU/Store/Day). The resulting URP values for each SKU/Store combination are then aggregated to a SKU Group/Company/Week level.
End of Week Inventory at CrossDocks	End of Week Inventory at CrossDocks represents the sum a SKU's Projected Inventory on the last day of the week at all warehouses with a warehouse type of CrossDocks.
End of Week Inventory at Deconsolidation Center	End of Week Inventory at Deconsolidation Center represents the sum of a SKU's Projected Inventory on the last day of the week at all warehouses with a warehouse type of Deconsolidation Center.
End of Week Inventory at RDCs	End of Week Inventory at RDCs represents the sum a SKU's Projected Inventory on the last day of the week at all warehouses with a warehouse type of RDC.
Expected Receipts from Vendors	Expected Receipts from Vendors shows the total inventory on order from vendors to warehouses and stores for any direct to store shipments.
Forecasted Receipts from Vendors	Forecasted Receipts from Vendors shows the total planned receipts from vendors to warehouses and stores for any direct to store shipments.
Forecast to Sell-Through %	Forecast to Sell-Through % contains the percentage of actual sales (historical weekly sales) to forecasted sales (forecasted demand at the week level).
Forecasted Weekly Sales	Forecasted Weekly Sales represents the total forecasted weekly sales (including customer orders) for a given SKU Group.
Forecasted Weeks of Supply	Forecasted Weeks of Supply represents the forecasted weeks of cover. It is calculated by dividing Saleable Inventory by Forecasted Avg Weekly Sales, where Forecasted Avg Weekly Sales is calculated as Forecasted Weekly Sales divided by the Number Of Weeks Forecast.
Inventory per Store	Inventory per Store represents the average inventory level per store, excluding demo stock. It is calculated as the Saleable Inventory divided by the number of stores.

Measure Label	Description
Number Of Stores	Number Of Stores represents the total number of stores for this SKU Group.
Number Of Weeks Forecast	Number Of Weeks Forecast represents the number of weeks in the future (including present week) over which Forecasted Avg Weekly Sales is calculated.
Retail Price	Retail Price is the product's retail price. Note: Retail Price is loaded from an external system.
Saleable Inventory	Saleable Inventory represents the amount of inventory that can actually be sold. It is calculated as the aggregated end of week projected inventory minus the aggregated end of week demo stock.
Sales Week	Sales Week represents the calendar week number. For example, week 5 is the 5th week of the year.
Sum of RDC Avg Weekly Sales	Sum of RDC Avg Weekly Sales contains the aggregated total of average weekly sales for an RDC (Regional Distribution Center) warehouse.
Sum of Stores Avg Weekly Sales	Sum of Stores Avg Weekly Sales contains the aggregation of an item's average weekly sales across all stores.
Total Avg Weekly Sales	Total Avg Weekly Sales contains the Sum of SKU of RDC Avg Weekly Sales and SKU Sum of Stores Avg Weekly Sales.
Tracking Sales	Tracking Sales estimates sales for the current week based on week-to-date sales. First, average daily sales is calculated by dividing the week-to-date sales by the number of days week-to-date (Sunday through the day prior to the current day). Next, the average daily sales are multiplied by 7, resulting in the SKU Tracking Sales.

SRP Exception Summary Tab

SRP Exception Summary (Corporate/SKU) Worksheet

This worksheet allows the user to review alert summary data at the Corporate/SKU level.

SRP Exception Summary (Corporate/SKU) Worksheet

This worksheet contains the following read-only measures.

Measure Label	Description
Ranged Stock Pts	Ranged Stock Pts contains the total number of stores across company available to receive and sell items from the previous night's batch run.
Yesterdays Availability	Yesterdays Availability is the percentage of stores across company for which this product was available to sell. In other words the percentage of stores that did not have stock outs the previous night. It is calculated as 1 minus the ratio of stores out of stock last night to the total number of stores available to sell the product.
Yesterdays Forecast	Yesterdays Forecast contains the sum of the forecasted demand for this product for the previous night across all stores (company level).

SRP Exception Summary (Weather Region/SKU) Worksheet

This worksheet allows the user to review alert summary data at the Weather Region/SKU level.

SRP Exception Summary (Weather Region/SKU) Worksheet

This worksheet contains the following read-only measures.

Measure Label	Description
Ranged Stock Pts Weather	Ranged Stock Pts contains the total number of stores across Weather Region available to receive and sell items from the previous night's batch run.
Yesterdays Availability Weather	Yesterdays Availability is the percentage of stores across Weather Region for which this product was available to sell. In other words the percentage of stores that did not have stock outs the previous night. It is calculated as 1 minus the ratio of stores out of stock last night to the total number of stores in this region available to sell the product.
Yesterdays Forecast Weather	Yesterdays Forecast contains the sum of the forecasted demand for this product for the previous night across all stores in this region.

SRP Exception Summary (Store Format/SKU) Worksheet

This worksheet allows the user to review alert summary data at the Store Format/SKU level.

SRP Exception Summary (Store Format/SKU) Worksheet

This worksheet contains the following read-only measures.

Measure Label	Description
Ranged Stock Pts Format	Ranged Stock Pts contains the total number of stores with this format available to receive and sell items from the previous night's batch run.
Yesterdays Availability Format	Yesterdays Availability is the percentage of stores with this format for which this product was available to sell. In other words the percentage of stores that did not have stock outs the previous night. It is calculated as 1 minus the ratio of stores out of stock last night to the total number of stores in this region available to sell the product.
Yesterdays Forecast Format	Yesterdays Forecast contains the sum of the forecasted demand for this product for the previous night across all stores with this format.

SRP Overstock Alert Summary Tab

SRP Overstock Details (SKU/Store/Day) Worksheet

The SRP Overstock Details Worksheet displays detailed overstock information at the SKU/Store/Day level.

	04/01/06	04/02/06	04/03/06	04/04/06
Cases Per Pallet	0	0	0	0
Direct Supply Point Flag	☐	☐	☐	☐
Stock Cover Days	0.00	0.00	0.00	0.00
Store Demand Forecast	100.00	100.00	75.00	50.00
Store Expected Receipts	0.00	0.00	0.00	0.00
Store In Transits	0.00	0.00	0.00	0.00
Store On Orders	0.00	0.00	0.00	0.00
Store Ordering Pack Size	1.00	1.00	1.00	1.00
Store Projected Inventory	0.00	0.00	0.00	325.00
Store Source Label	W1090 - MIT	W1090 - MIT	W1090 - MIT	W1090 - MIT

SRP Overstock Details (SKU/Store/Day) Worksheet

This worksheet contains the following read-only measures.

Measure Label	Description
Cases Per Pallet	The Cases Per Pallet measure indicates the pallet multiple for the source warehouse.
Direct Supply Point Flag	The Direct Supply Point Flag indicates whether the supply point is being sourced directly from a supplier.
Stock Cover Days	Stock Cover Days is calculated as the number of days the store's current inventory will cover demand.
Store Demand Forecast	The Store Demand Forecast is the forecast of the store's future sales. Note: Demand Forecast is loaded from an external forecasting system.
Store Expected Receipts	Store Expected Receipts (ER) are orders that have already been executed and therefore need to be considered when planning future orders for a store. Store Expected Receipts is the sum of in-transits and on orders. Note: In-transits and on orders s are loaded to SRP from an external system.
Store Intransits	Store Intransits represents Inventory in transit from warehouses and suppliers to store. Note: This measure is loaded from an external system.
Store On Orders	Store On Orders are fixed orders currently being processed for delivery to store either from warehouses or directly from suppliers Note: This measure is loaded from an external system.

Measure Label	Description
Store Ordering Pack Size	The Store Ordering Pack Size represents the primary pack size to be used when ordering a SKU for a store (either from a warehouse or from a supplier). Note: Store Ordering Pack Size is loaded from Data Management online (DMo).
Store Projected Inventory	Store Projected Inventory (PI) is calculated in AIP batch and represents a projection of the opening inventory position for any day in the planning horizon at a specific store. None of that day's activities (either receipts or demand) are reflected in PI, and so it is often referred to as a "beginning of day" position. PI on a given day is calculated as the PI of the previous day plus the net impact of all demand and replenishments on the previous day. Previous day demand consists of forecasted demand plus any customer orders (CO) on that day. Previous day replenishments consist of Expected and Planned Receipts.
Store Source Label	The Store Source Label identifies the source from which this store receives inventory.

SRP Overstock Alert (SKU)

This worksheet allows the user to review pertinent information regarding the SKU's status.

SRP Overstock Details (SKU/Store/Day) Worksheet

This worksheet contains the following read-only measures.

Measure Label	Description
Corporate Discontinuation Date	The Corporate Discontinuation Date measure indicates the date measure by when the SKU pack size is planned for discontinuation at the corporate level.
Promotional SKU	The Promotional SKU measure denotes whether a SKU is promotional.

SRP Maintenance Workbook

The SRP Maintenance workbook is used to modify level replenishment parameters. Any parameters maintained for a specific SKU in this workbook will override any values in equivalent parameters at global (dept) or default (sub-class/store format). The values set here define the details of the replenishment method used and are used to generate a replenishment plan.


This workbook contains worksheets that are grouped into four tabs with the associated worksheets:

- SRP Exception Parameters (SKU/Store/Day) tab
 - RP Exception Parameters (SKU/Store/Day)
- SRP Exception Parameters (SKU/Store) tab
 - SRP Exception Parameters (SKU/Store)
- SRP Exception Parameters (SKU/Store/Week) tab
 - SRP Exception Parameters (SKU/Store/Week)
- SRP Exception Parameters (SKU) tab
 - SRP Exception Parameters (SKU)

SRP Maintenance Wizard

Available SKUs


The dialog box for Available SKUs displayed below will show a list of all SKUs in the AIP domain. The user's previous selections are already selected. The user has the ability to re-select which SKUs will be accessed in the workbook. The positions default to the SKU level. Standard RPAS functionality is available for this particular wizard page.



SRP Maintenance Wizard – Available SKUs

Available Stores


The dialog box for Available Stores displayed below will show a list of all Stores in the AIP domain. The user's previous selections are already selected. The user has the ability to re-select which Stores will be accessed in the workbook. The positions default to the Store level. Standard RPAS functionality is available for this particular wizard page.



SRP Maintenance Wizard – Available Stores

Available Days

The dialog box for Available Days displayed below will show a list of all dates in the AIP domain. The user's previous selections are already selected. The user has the ability to re-select which dates will be accessed in the workbook. The positions default to the day level. Standard RPAS functionality is available for this particular wizard page.



SRP Maintenance Wizard – Available Days

SRP Exception Parameters (SKU/Store/Day) Tab

SRP Exception Parameters (SKU/Store/Day) Worksheet

The SRP Exception Parameters (SKU/Store/Day) worksheet contains exception level parameter values that are used in generating and processing store replenishment plans.

	04/01/06	04/02/06	04/03/06	04/04/06
Base Store Promotion Presentation Stock	0.00	0.00	0.00	0.00
Store AWS Factor				
Store Boundary Stock				
Store Demo Stock				
Store Increment Percent				
Store Inventory Selling Days				
Store Max Safety Stock Days				
Store Max Safety Stock Units				
Store Max Stock				
Store Max Time Supply Days				
Store Min Safety Stock Days				
Store Min Safety Stock Units				
Store Min Stock				
Store Min Time Supply Days				
Store MSQ Constraint Indicator				
Store Percent of Pallet				

SRP Exception Parameters (SKU/Store/Day) Worksheet

The SRP Exception Parameters (SKU/Store/Day) worksheet contains writeable measures (unless otherwise noted) at the SKU/Store/Day level. The measures on this work sheet are time-phased at the day level. When data is entered on a specific date, that date becomes an 'effective date' for that measure. Once a value is entered on a date, the value will remain in effect until the value is changed to another valid value, or a special value is entered.

The following measures are displayed automatically when using the default template.

Measure Label	Description
Base Store Promotion Presentation Stock	The Base Store Promotion Presentation Stock represents the specified quantity for Store Promotion Presentation Stock before application of the End of Store Promotion Factor.

Measure Label	Description
Store AWS Factor	The AWS Factor allows SRP users to provide a numeric factor to be multiplied against the average weekly sales (AWS) to determine replenishment boundaries (safety stock, receipt point and receive up to level) for the Factor AWS replenishment method. Any positive number is valid. Special Values: ▪ -1 (Use Previous) ▪ -2 (Use Default) Example To calculate a safety stock that is 50% of the average weekly sales, the user would enter an AWS Factor of .5.
Store Boundary Stock	The Boundary Stock identifier allows SRP users to select the stock level to use in calculating the Store Receipt Point and Store Receive Up to Level. This stock level is a combination of Safety Stock, Presentation Stock and/or Promotional Presentation Stock based on the identifiers listed below. If the identifier contains “vs”, the greater value will be used. This parameter affects all replenishment methods. The user selects the boundary stock identifier from the following picklist options: ▪ SS vs PS + PPS ▪ SS vs PS ▪ SS vs PPS ▪ SS + PS + PPS ▪ SS + PS ▪ SS + PPS ▪ SS Where, SS = Safety Stock PS = Presentation Stock PPS = Promotional Presentation Stock The picklist default is SS vs PS + PPS. Example Selecting SS vs PS will add the greater of SS or PS to the calculated Store Receipt Point and Store Receive Up to Level values.
Store Demo Stock	Amount of stock that is not sellable due to use as demonstration product. Demo Stock is added to the RP and RUTL levels for each day. Any positive number, including zero, is valid. Special Values: ▪ -1 (Use Previous) ▪ -2 (Use Default)

Measure Label	Description
Store Increment Percent	The Increment Percent acts as a multiplier for minimum and maximum stock that is designed to handle temporary fluctuation in demand for items using Min/Max Replenishment Method. An increment percentage factor can be used to temporarily increase or decrease targeted stocking levels without altering the established MIN and MAX values. Any positive number, including zero, is valid. Special Values: ▪ -1 (Use Previous) ▪ -2 (Use Default) Example To use 120% of the Min and Max Stock, the user would enter an Increment Percent of 1.2.
Store Inventory Selling Days	The Inventory Selling Days parameter is used to specify the number of days of forecast quantity to be used when calculating the Receive up to Level (RUTL) with the Hybrid, Dynamic, Poisson and Loaded SS Dynamic Replenishment Methods. The RUTL calculation will use the forecast demand over the greater of Inventory Selling Days and Review Time. Inventory Selling Days can be used to avoid producing very small frequent orders. Any positive integer, including zero, is valid. Special Values: ▪ -1 (Use Previous) ▪ -2 (Use Default) Example To ensure an order will contain at least 14 days of supply, 14 would be entered as the number of Inventory Selling Days.
Store Max Safety Stock Days	The Max Safety Stock Days parameter is used to specify the maximum number of days of cover to be kept on hand as safety stock. If the user enters both Max Safety Stock Days and Max Safety Stock Units, the maximum safety stock boundary will use the larger of demand over max safety stock days and max safety stock units. Any positive integer, including zero, is valid. Special Values: ▪ -1 (Use Previous) ▪ -2 (Use Default) ▪ -3 (Unbounded) Example To ensure the maximum safety stock will contain at least 14 days of supply, 14 would be entered in Max Safety Stock Days. If Max Safety Stock Units is greater than 14 days of supply, max units would be used as the maximum safety stock, otherwise maximum safety stock would be the number of units required to cover 14 days of demand.

Measure Label	Description
Store Max Safety Stock Units	The Max Safety Stock Units parameter is used to specify the maximum amount of inventory to be kept on hand as safety stock. If the user enters both Max Safety Stock Days and Max Safety Stock Units, the maximum safety stock boundary will use the larger of demand over max safety stock days and max safety stock units. Any positive number, including zero, is valid. Special Values: ▪ -1 (Use Previous) ▪ -2 (Use Default) ▪ -3 (Unbounded) Example To ensure the maximum safety stock will contain at least 14 days of supply, 14 would be entered in Max Safety Stock Days. If Max Safety Stock Units is greater than 14 days of supply, max units would be used as the maximum safety stock, otherwise maximum safety stock would be the number of units required to cover 14 days of demand.
Store Max Stock	Max Stock is only used in the Min/Max Replenishment Method. It represents the maximum stock level in units that are desired on hand to satisfy demand. The receipt plan quantity is calculated to bring Net Inventory up to MAX. Any positive number, including zero, is valid. Special Values: ▪ -1 (Use Previous) ▪ -2 (Use Default) ▪ -3 (Unbounded)
Store Max Time Supply Days	Max Time Supply Days is only used in the Time Supply Replenishment Method. It represents maximum stock level in terms of number of days cover that that are desired on hand to satisfy demand. The receipt plan quantity is calculated to bring Net Inventory up to Maximum Time Supply Days of cover. Any positive integer, including zero, is valid. Special Values: ▪ -1 (Use Previous) ▪ -2 (Use Default) Example To ensure an order will bring the inventory level up to 14 days of supply, 14 would be entered in Max Time Supply Days.

Measure Label	Description
Store Min Safety Stock Days	The Min Safety Stock Days parameter is used to specify the minimum number of days of cover to be kept on hand as safety stock. If the user enters both Min Safety Stock Days and Min Safety Stock Units, the minimum safety stock boundary will use the larger of demand over min safety stock days and min safety stock units. Any positive integer, including zero, is valid. Special Values: ▪ -1 (Use Previous) ▪ -2 (Use Default) Example To ensure the minimum safety stock will contain at least 7 days of supply, 7 would be entered in Min Safety Stock Days. If Min Safety Stock Units is greater than 7 days of supply, min units would be used as the minimum safety stock, otherwise minimum safety stock would be the number of units required to cover 7 days of demand.
Store Min Safety Stock Units	The Min Safety Stock Units parameter is used to specify the minimum amount of inventory to be kept on hand as safety stock. If the user enters both Min Safety Stock Days and Min Safety Stock Units, the minimum safety stock boundary will use the larger of demand over min safety stock days and min safety stock units. Any positive number, including zero, is valid. Special Values: ▪ -1 (Use Previous) ▪ -2 (Use Default) Example To ensure the minimum safety stock will contain at least 7 days of supply, 7 would be entered in Min Safety Stock Days. If Min Safety Stock Units is greater than 7 days of supply, min units would be used as the minimum safety stock, otherwise minimum safety stock would be the number of units required to cover 7 days of demand.
Store Min Stock	Min Stock is only used in the Min/Max Replenishment Method. It represents the minimum stock level in units that are desired on hand to satisfy demand. Min Stock is used in determining the inventory level at which a replenishment is triggered. Any positive number, including zero, is valid. Special Values: ▪ -1 (Use Previous) ▪ -2 (Use Default)

Measure Label	Description
Store Min Time Supply Days	Min Time Supply Days is only used in the Time Supply Replenishment Method. It represents minimum stock level in terms of number of days cover that that are desired on hand to satisfy demand. Min Time Supply Days of cover is used in both safety stock and receipt point calculations. Any positive integer, including zero, is valid. Special Values: ▪ -1 (Use Previous) ▪ -2 (Use Default) Example To ensure a minimum inventory level that will cover 7 days of supply, 7 would be entered in Min Time Supply Days.
Store MSQ Constraint Indicator	The Store MSQ Constraint Indicator indicates when the MSQ should be applied as a constraint during ordering decisions. If unspecified, the indicator is considered to be "On" and thus, MSQ will be used as a constraint.
Store Percent of Pallet	Percent of pallet is used to determine if the Ideal Receipt Quantity for replenishment should be rounded to a full pallet. It represents the percentage threshold that case demand must exceed in order for pallet rounding to occur. Valid values are 0 through 1. Special Values: ▪ -1 (Use Previous) ▪ -2 (Use Default) Example If an SRP user wants to round an order up to a pallet if the case demand is greater than 75 percent of a pallet, the user would enter .75 in Percent of Pallet.
Store Promotion Presentation Stock Override Flag	The Store Promotion Presentation Stock Override Flag indicates what value should be used for Store Promotion Presentation Stock. When the override flag is turned on ("TRUE"), the Store Promotion Presentation Stock equals zero ("0").
Store Repl Method	The choice of Replenishment Method determines the type of calculations that will be used in generating a store replenishment method. The user selects the Replenishment Method from the following picklist options: ▪ Min/Max ▪ Time Supply ▪ Dynamic ▪ Hybrid ▪ No Replenishment ▪ Poisson Replenishment ▪ Loaded SS Dynamic ▪ ales Week Range ▪ Factor AWS The picklist default is No Replenishment.

Measure Label	Description
Store Rounding Method	The Rounding Method is used when pack rounding the ideal receipt quantity (IRQ). The user selects the Rounding Method value from the following picklist options: ▪ Unspecified ▪ Order Pack ▪ Normal Unspecified defaults to 'Normal'.
Store Rounding Threshold	The Rounding Threshold represents the portion of a pack above which the replenishment plan is rounded up and below which it is rounded down. A zero threshold will always round up, and a threshold of 1 will always round down. If no value is entered, rounding threshold defaults to 1. Valid values are 0 through 1. Special Values: ▪ -1 (Use Previous) ▪ -2 (Use Default) Example If an SRP user wants to round an order up to a pack if the demand is greater than 25 percent of a pack, the user would enter .25 in Rounding Threshold.
Store Safety Stock Level Factor	The Safety Stock Level Factor represents the amount of additional safety stock to carry in anticipation of unpredictable events (for instance, weather changes) or to provide additional safety stock during a special promotion or event. This will provide a temporary lift in the Receipt Point (RP) and Receive Up To Level (RUTL) values. The Safety Stock Level Factor is used in Time Supply, Hybrid, Poisson, Dynamic and Loaded SS Dynamic Replenishment Methods. Example To increase safety stock by 25 units, the user would enter a Safety Stock Level Factor of 25. Negative values may also be entered to decrease the safety stock level.
Store Service Level	The Service Level is used in the safety stock calculations for the Dynamic and Poisson replenishment methods. It is defined as the percentage of demand that the stock should be able to meet demand. Valid values are 0 through 1. Special Values: ▪ -1 (Use Previous) ▪ -2 (Use Default) Example If an SRP user wants to carry enough safety stock to maintain a 90% customer service level, the user would enter .90 in Service Level.

Measure Label	Description
Store Shelf Capacity	Shelf capacity is the amount of stock to fill a shelf to the desired maximum level. If the Shelf Capacity Flag is set to 'Yes', the shelf capacity is used to cap the receipt point and receive up to level. Any positive number, including zero, is valid. Special Values: -1 (Use Previous) -2 (Use Default)
Store Shelf Capacity Flag	The Shelf Capacity Flag is used to determine if the receipt point and receive up to level should be capped by the shelf capacity. The user selects the Shelf Capacity Flag value from the following picklist options: - Yes - No - Default Example Selecting 'Yes' will cause SRP to use shelf capacity to cap receipt point and receive up to level. Selecting 'No' or 'Default' indicates SRP will not use shelf capacity to cap receipt point and receive up to level.
Store Time Supply Horizon	The Time Supply Horizon parameter is used to specify days of forecast in order to calculate a rate of sale. If a time supply horizon is specified, the rate of sale is used instead of the actual forecast when calculating demand over the time supply days for inventory target level calculations for the Time Supply Replenishment Method. Any positive integer, including zero, is valid. Special Values: -1 (Use Previous) -2 (Use Default) Example To calculate a Rate of Sale (ROS) over a one week period, enter a value of 7 in Time Supply Horizon. The (ROS) is then calculated by summing the forecasted sales over the 7 days and dividing that number by 7.
Store Weekly Sales Max	Maximum stock boundary for the Factor AWS, Sales Date Range, and Loaded SS Dynamic replenishment methods. Any positive number, including zero, is valid. Special Values: -1 (Use Previous) -2 (Use Default) -3 (Unbounded)
Store Weekly Sales Min	Minimum stock boundary for the Factor AWS, Sales Date Range, and Loaded SS Dynamic replenishment methods. Any positive number, including zero, is valid. Special Values: -1 (Use Previous) -2 (Use Default)

Measure Label	Description
User Specified Store Presentation Stock	Presentation Stock is the minimum amount of stock in units desired to have on hand for display/sales purposes. Presentation Stock may be taken into consideration when calculating the Receipt Point and Receive up to Level, depending on the Boundary Stock selected. Any positive number, including zero, is valid. Special Values: ▪ -1 (Use Previous) ▪ -2 (Use Default)

Hidden Workbook Measures

The following measures are hidden when using the default template. They can be displayed and maintained by using the Insert measure function of RPAS.


Measure Label	Explanation
Store Acceptable Loss	Acceptable Loss represents the percentage of a case that is acceptable to lose from spoilage in order to prevent stock outs. While Acceptable Loss is the value maintained in the database, SRP users can change either Acceptable Loss or Spoilage Threshold. If a user edits Acceptable Loss, Spoilage Threshold will be disabled for update and Spoilage Threshold is calculated as 1 minus Acceptable Loss. Valid values are 0 through 1. Special Values: ▪ -1 (Use Previous) ▪ -2 (Use Default) Example If an SRP user finds it acceptable to lose 10% from spoilage, the user would enter .10 in Acceptable Loss.
Store Minimum Presentation Stock	The Store Minimum Presentation Stock indicates the minimum presentation quantity to be used in the calculation of store presentation stock. Any value greater than or equal to zero ("0") is acceptable.
Store Presentation Stock Override Flag	The Store Presentation Stock Override Flag is used when calculating the Store Presentation Stock to indicate whether the override quantity should be used. When the Store Global Default Presentation Stock Override Flag is turned on ("TRUE"), the override quantity should be used.
Store Presentation Stock Override Quantity	The Store Presentation Stock Override Quantity is the value used when calculating Store Presentation Stock if the override flag is turned on ("TRUE").
Store Spoilage Threshold	Spoilage threshold is used as a pack rounding constraint. While Acceptable Loss is the value maintained in the database, SRP users can change either Acceptable Loss or Spoilage Threshold. If a user edits Default Spoilage Threshold, Acceptable Loss will be disabled for update and Acceptable Loss is calculated as 1 minus Spoilage Threshold. Valid values are 0 through 1. Special Values: ▪ -1 (Use Previous) ▪ -2 (Use Default) Example If an SRP user wants to round a pack up if the spoilage threshold is greater than 90%, the user would enter .9 in Spoilage Threshold.

Measure Label	Explanation
Store Weekly Base Sales Forecast %	The Store Weekly Base Sales Forecast indicates what percentage of the Weekly Base Sales Forecast should be used in the calculation of store presentation stock. Values between 0 and 1 (inclusive) are valid. Zero ("0") indicates that 0% of the forecast should be used and "1" indicates that 100% of the forecast should be used.

SRP Exception Parameters (SKU/Store) Tab

SRP Exception Parameters (SKU/Store) Worksheet

The SRP Exception Parameters (SKU/Store) worksheet contains exception level parameter values that are used in generating and processing store replenishment plans.



SRP Exception Parameters (SKU/Store) Worksheet

The SRP Exception Parameters (SKU/Store) worksheet contains writeable measures (unless otherwise noted) at (SKU/Store) level.

The following measures appear automatically when using the default template.

Measure Label	Explanation
Store End Date Range	The End Date Range parameter allows SRP users to select the date that should be used as the ending point for determining the historical sales data used by the "Sales Date Range" and "Factor AWS" replenishment methods. A pop-up calendar can be used to select the desired end date. Select a date less than or equal to the current date.
Store Start Date Range	The Start Date Range parameter allows SRP users to select the date that should be used as the starting point for determining the historical sales data used by the "Sales Date Range" and "Factor AWS" replenishment methods. A pop-up calendar can be used to select the desired start date. Select a date less than or equal to the current date.

Hidden Workbook Measures

The following measures are hidden when using the default template. They can be displayed and maintained by using the Insert measure function of RPAS.

Measure Label	Explanation
Store Freshness Flag	The Freshness Flag is only used when the Inventory Aging Limit is set (indicating the SKU has a product life). When the Freshness Flag is "TRUE," SRP will ensure that a store replenishment plan is generated for at least the customer orders over Review Time (CORT) regardless of the inventory position.
Store Supplier Compliance Safety Stock	The Supplier Compliance Safety Stock parameter represents a 'number of days of supply' additional safety stock to deal with supplier and supply chain compliance issues. The days covered begins with the latest of Review Time or Inventory Selling Days. The calculated Supplier Compliance Safety Stock Units is added on to the Safety Stock. Any positive number, including zero, is valid. Example To add an addition 7 days of supply, 7 would be entered in Supplier Compliance Safety Stock.

SRP Exception Parameters (SKU/Store/Week) Tab

SRP Exception Parameters (SKU/Store/Week) Worksheet

The SRP Exception Parameters (SKU/Store/Week) worksheet contains exception level parameter values that are used in generating and processing store replenishment plans.

SRP Exception Parameters (SKU/Store/Week) Worksheet

The SRP Exception Parameters (SKU/Store/Week) worksheet contains writeable measures (unless otherwise noted) at the SKU/Store/Week level.

The following measures appear automatically when using the default template.

Measure Label	Explanation
Store Roll Weeks	The Roll Weeks parameter indicates whether SRP logic should automatically roll the start and end date range settings forward one week or not. Roll weeks is used in the Factor AWS Sales Date Range Replenishment Methods. The user selects the Roll Weeks value from the following picklist options: ▪ Yes ▪ No ▪ Default Example Selecting 'Yes' will cause the start and end date to roll forward one week, allowing the user to keep the weekly historical sales at the same relative distance in the past. Selecting 'No' will not move the start and end date forward allowing the user to use the same weekly historical sales as the system moves forward in time.

SRP Exception Parameters (SKU) Tab

SRP Exception Parameters (SKU) Worksheet

The SRP Exception Parameters (SKU) worksheet contains exception level parameter values that are used in generating and processing store replenishment plans.

SRP Exception Parameters (SKU) Worksheet

The SRP Exception Parameters (SKU) worksheet contains writeable measures (unless otherwise noted) at SKU level.

The following measures appear automatically when using the default template.

Measure Label	Explanation
Reconciliation Method	The Reconciliation Method is used to determine if reconciliation will occur on a day by day basis or over time. The user selects the Roll Weeks value from the following picklist options: ▪ Day-on-Day ▪ Reconcile Over Time Example Selecting 'Day-on-Day' will cause reconciliation from the source warehouse or supplier to occur for each day in the planning horizon. Day-on-Day reconciliation will ship the inventory out to the store or warehouse destination quickly, considering only those destination stores or warehouses where a shipment today would arrive on the available to plan (ATP) day. While this method may ship the inventory sooner than the 'Reconcile Over Time' method, stores or warehouses with ATP days later in the review period may receive less inventory than those with ATP days earlier in the review period. Selecting 'Reconcile Over Time' will cause reconciliation from the source warehouse or supplier to occur over each review period in the planning horizon. Reconcile Over Time allocation may cause some inventory to be retained at the source warehouse or supplier for shipment later in the review period. While this method may not ship the inventory as quickly as the 'Day-on-Day' method, all ATP days within the review period for all stores and warehouses will be considered equally in the inventory allocation.
Store Use Inventory Aging Flag	The Store Inventory Aging Flag indicates whether the Store Inventory Aging Limit is used in the expected spoilage calculation. Valid values are "TRUE" or "FALSE".

SRP Implementation Parameters Workbook

The SRP Implementation Parameters Workbook is required to maintain SRP implementation parameter settings that are used by the entire package (scalar level).

Because values in this workbook are used by the entire SRP system, it is recommended that security is set to allow a single or limited number of super users access to this workbook.

Note: Since this workbook is scalar, no wizard is required.

This workbook contains one worksheet that is located under a single tab:

- Implementation Parameters tab
 - Implementation Parameters Worksheet

SRP Implementation Parameters Worksheet

The Implementation Parameters worksheet contains SRP implementation parameter settings that are used by the entire package (scalar level).

SRP Implementation Parameters	
Calculated Store Presentation Stock Indicator	☐
Daily Forecast Length	0
Days Beyond Planning Horizon	7
Days Of Ignored Availability	1
Expected Spoilage Calculation Indicator	☒
Inventory Capping Forecast Days	7
Inventory Tracking Level	Each
Secondary Delivery Window	0
SPQ Date Type	Ship Date
Spread Inventory Flag	☐
Store Inventory Aging Limit	0

Measure ← →

Implementation Parameters Worksheet

This worksheet contains the following measures at the scalar, or global, level. All measures are writeable unless noted otherwise.

Measure Label	Description
Calculated Store Presentation Stock Indicator	Boolean indicator to denote when the calculated store presentation stock should be factored into the calculation of Store Presentation Stock.

Measure Label	Description
Daily Forecast Length	Note: Forecasts are loaded to SRP from an external system as daily forecasts, weekly forecasts, or a combination of daily and weekly forecasts. The Daily Forecast Length is used to specify the number of days of daily forecasts to use when loading forecasts. Valid values are -1, 0, and “n”, where “n” is any positive number. -1 = Load all daily forecasts 0 = Load all weekly forecasts n = Load daily forecasts for the first “n” days Example: To load daily forecasts for the first two weeks, enter “14” in Daily Forecast Length.
Days Beyond Planning Horizon	The Days Beyond Planning Horizon Parameter represents the number of days SRP will look forward to find the next ATP day after the end of the planning horizon. SRP will use the data between the end of the planning horizon and the next ATP day to calculate the receipt plan for the last ATP day. No plan is calculated on the ATP day beyond the planning horizon. If SRP does not find an ATP day in the period from the end of the planning horizon through the days beyond the planning horizon, the receipt plan calculations will use data through the days beyond planning horizon to plan the last receipt. Any positive number, including zero, is valid. Example: If the majority of items are available to plan 2 weeks or less, a user could enter “14” in Days Beyond Planning Horizon. This would allow the system to find the next ATP day in most cases and have the required data to calculate an accurate receipt plan on the last ATP day within the horizon.
Days of Ignored Receipts	The Days of Ignored Receipts indicates how many days of availability should be ignored when determining the end of the first Reconciliation Period. This parameter should never be set to less than 1 day. (Read Only)
Expected Spoilage Calculation Indicator	The Expected Spoilage Calculation Indicator indicates when Expected Spoilage (ES) calculations should be performed. The default is “true”, which indicates that ES calculations should be performed where product life is deemed relevant for a particular SKU. If value set to “false”, ES is considered to be “0” in projected and net inventory calculations.
Inventory Capping Forecast Days	Inventory Capping Forecast Days is an implementation parameter representing the number of days over which forecasts are summed when determining the Inventory Cap Forecast for a SKU. The Inventory Cap Forecast will be used to recommend SKU Caps proportionally for a department. The Inventory Capping Forecast Days should be set to value that would represent a fair split of the stores forecast. Inventory Capping Forecast Days must be a positive integer; the default value is 7 days.

Measure Label	Description
Inventory Tracking Level	Inventory Tracking Level determines the level at which planning occurs. The available options are packs or eaches. Example: Selecting "Packs" will cause AIP to plan in pack-sizes. Selecting "Eaches" will cause AIP to plan in eaches, where all inventory and supply is considered available in singles, and orders are generated using the order multiple and pack sizes as the appropriate rounding multiples. Note: A change to the Inventory Tracking Level parameter after implementation is not supported. If business requirements require a change to tracking level, analysis of the impact and other changes which may be required can be provided by Services.
Secondary Delivery Window	The Secondary Delivery Window indicates how many days earlier than the day of a shortage a delivery can be received from a Secondary Source to meet that shortage. (Read only)
SPQ Date Type	The SPQ Date Type determines whether SPQ constraint is applied against the ship date or receipt date. The user selects the SPQ Date Type from the following picklist options: ▪ Ship Date ▪ Receipt Date
Spread Inventory Flag	The Spread Inventory Flag specifies if it is desirable to spread inventory across multiple delivery opportunities of a single destination during Primary Reconciliation. (Read Only)
Store Inventory Aging Limit	The Store Inventory Aging Limit defines the upper threshold in days which product life. When the product life is less than the aging limit, inventory aging processing will occur. Any positive number, including zero, is valid. Example: To use inventory aging only on items with a product life of one week or less, enter "7" as the Store Inventory Aging Limit. This ensures that any item with a product life greater than 7 days will not be considered in the inventory aging calculation.

SRP Inventory Capping Parameters Workbook

Inventory Capping Parameters is required to set up the basic Inventory Capping parameters. This workbook is used to maintain the SKU Capping Flag, Relative Space per Unit, and Department Capacity. The workbook contains a single tab (Inventory Capping Parameters) which in turn contains three worksheets:

- Inventory Capping Parameters tab
 - Inventory Capping Parameters (Subclass) Worksheet
 - Inventory Capping Parameters (SKU) Worksheet
 - Department Capacity Worksheet

The workbook is global domain enabled and not available locally.

Note: Today must be included in the workbook.

Available Departments

The dialog box for Available Departments, displayed below, will show a list of all Departments in the AIP domain. The user's previous selections are already selected. The user has the ability to reselect which Departments will be accessed in the workbook. The positions default to the Dept level. Standard RPAS functionality is available for this particular wizard page.

SRP Inventory Capping Parameters Wizard

Available Departments

- ☐ Activewear
- ☐ SEATING
- ☐ BINDERS
- ☐ BREAKROOM
- ☐ OFFICE ESSENTIALS
- ☒ MONITORS/LCD PROJ.
- ☐ PAPER
- ☐ CALCULATOR/ORGANIZER
- ☐ SCHOOL SUPPLIES
- ☐ SOFTWARE/BOOKS
- ☐ SURGE/CABLES

☐ Synchronize hierarchies

Selected Departments

- MONITORS/LCD PROJ.


Position Query Definitions

Cancel <Back Next> Finish Help

SRP Inventory Capping Parameters Wizard – Available Departments

Available Stores


The dialog box for Available Stores displayed below will show a list of all Stores in the AIP domain. The user's previous selections are already selected. The user has the ability to reselect which Stores will be accessed in the workbook. The positions default to the Store level. Standard RPAS functionality is available for this particular wizard page.



SRP Inventory Capping Parameters Wizard – Available Stores

Available Days

The dialog box for Available Days displayed below will show a list of all dates in the AIP domain. The user's previous selections are already selected. The user has the ability to reselect which dates will be accessed in the workbook. The positions default to the day level. Standard RPAS functionality is available for this particular wizard page.



SRP Inventory Capping Parameters Wizard – Available Days

Inventory Capping Parameters (Subclass) Worksheet

This worksheet allows maintenance of parameters at the subclass level that are relative to the SKU, specifically a capping flag indicating whether or not a SKU is capped, and the relative space per unit measure indicating the relative size of the space the SKU occupies.

	Default Capping Flag	Default Relative Space per Unit
CRT MONITORS	Yes	1.00
FLAT CRT MONITORS	Yes	0.50
LCD MONITORS	Yes	1.00
PORT. LCD PROJECTOR	Yes	0.50

Product < >

Inventory Capping Parameters (Subclass) Worksheet


This worksheet contains the following writeable measures:

Measure Label	Explanation
Default Capping Flag	The Capping Flag is used to determine if inventory caps apply to subclasses and SKUs. Valid values are "Yes" (capped), or "No" (not capped). The Capping Flag entered at the subclass level acts as a default value. The default will be used for all SKUs in the subclass that have not been updated with an override. In other words, if a subclass has a capping flag value of "Yes" (capped), all SKUs in that department will have a value of "Yes" unless a user changes a specific SKU to "No". Once that SKU has been overridden, the SKU level capping flag becomes a hard value. Thus, when a reclassification occurs, the hard value at the SKU level will be retained. This means changing a capping flag at the subclass level will not change the capping flag for SKUs with overrides in that subclass. SKUs without overrides will use the new subclass values. The Capping Flag will default to "Not Set". The behavior of Not Set would be the same as "No".

Measure Label	Explanation
Default Relative Space per Unit	Relative Space per Unit represents the relative amount of space one unit of the SKU will occupy. For example, a washer = 1, a refrigerator =2, etc. This measure will be manually entered in the Inventory Capping Parameters Worksheet at either the subclass or SKU level. This measure will be used when recommending SKU Caps. The Relative Space per Unit entered at the subclass level acts as a default value. The default will be used for all SKUs in the subclass that have not been updated with an override. In other words, if a subclass has a Relative Space per Unit value of 1, all SKUs in that department will have a value of 1 unless a user changes a specific SKU. Once that SKU has been overridden, the SKU level Relative Space per Unit becomes a hard value. Therefore, when a reclassification occurs, the hard value at the SKU level will be retained. This means changing a relative space at the subclass level will not change the relative space for SKUs with overrides in that subclass. SKUs without overrides will use the new subclass values. Relative Space per Unit is a real measure and must be greater than zero.

Inventory Capping Parameters (SKU) Worksheet

This worksheet allows maintenance of parameters that are relative to the SKU, specifically a capping flag indicating whether or not a SKU is capped, and the relative space per unit measure indicating the relative size of the space the SKU occupies.



	Measure	
	Capping Flag	Relative Space per Unit
100035032 - MONITOR,CRT,A91F+, ULTRA BRG	Yes	0.00
100036035 - DUMMY,PROJECTOR,PJ551 VIEWS	No	0.00
100037020 - PROJECTOR VIEWSONIC PJ551 LC		0.00
100044001 - MONITOR,VA521,15",LCD DISPLA'		0.00
100045003 - MONITOR,ULTRA BRIGHT,17",VWS		0.00
100045011 - MONITOR,VA721 17" LCD,VIEWSN		0.00
100045020 - MONITOR,VX710 17" LCD,VIEWSN		0.00
100046006 - MONITOR,VX910 19" LCD,VIEWSN		0.00
100049004 - AIP MONITOR,ULTRA BRIGHT,17",V		0.00

Product < [icon] >

Inventory Capping Parameters (SKU) Worksheet

This worksheet contains the following writeable measures:

Measure Label	Explanation
Capping Flag	If the Capping Flag for a SKU is "Yes" (capped), the item will have SKU Caps applied at the store when calculating the SRP replenishment plan. SKUs with a Capping Flag of "Yes" when the Inventory Cap Management Workbook is opened will be automatically included in the workbook build. If the Capping Flag for a SKU is "No" (not capped), caps will not be calculated for the SKU and a normal replenishment plan will be calculated for this item, with no inventory capping logic applied. The value at the SKU level is always used and only SKU level settings are considered during cap calculations and replenishment plan calculations.
Relative Space per Unit	Relative Space per Unit represents the relative amount of space one unit of the SKU will occupy. For example, a washer = 1, a refrigerator =2, etc. The value at the SKU level is always used and only SKU level settings are used in the cap calculations. Relative Space per Unit is a real measure and must be greater than zero.

Department Capacity Worksheet

The Department Capacity Worksheet at the Dept/Store/Day level allows maintenance of the Department Capacity at a store, indicating the amount of space allocated to this department for a store.

Product	Location	Department Capacity	Calendar
MONITORS/LCD PROJ.	S1000000001 - Minneapolis		
		03/31/06	04/01/06
Active Department Capacity		0.00	0.00
Department Capacity		35.00	0.00
Department Capacity (expanded)		35.00	35.00

Inventory Capping Parameters – Department Capacity Worksheet

The Department Capacity Worksheet contains the following three measures at the Dept/Store/Day level:

Measure Label	Explanation
Active Department Capacity	The Active Department Capacity represents the sum of all Active SKU Caps (space) for this department. Active SKU Caps (space) are calculated as the Active SKU Caps (units) multiplied by the corresponding Relative Space per Unit. (Read only)
Department Capacity	The Department Capacity is a time-phased measure representing the capacity in a store for this department. Department Capacity is manually maintained by the user on this worksheet as space values. The Department Capacity is required to generate calculated caps. The size of a space value is determined by the client and should be consistent within each department. SKUs are given a relative space per unit, indicating how much space is required to display an item relative to other items within the department. The Department Capacity is entered on the day it becomes effective. That capacity will remain in effect until the date a new capacity is entered. For example, Example: If the user enters a department capacity of 6 on January 19, 2007 and a department capacity of 5 on January 23, 2007, department capacity used in calculations (Expanded Department Capacity) would be 6 from January 19th through January 22nd, and 5 from January 23rd through the end of the workbook.
Department Capacity (Expanded)	The Expanded Department Capacity displays the actual values that will be used in the SKU Cap calculations across time in the workbook based on the values entered in the Department Capacity measure. The Expanded Department Capacity is calculated in the workbook and cannot be updated by the user. (Read only)

SRP Inventory Capping Management Workbook

The SRP Inventory Capping Management workbook is required to view and maintain SKU Caps. This workbook contains the following two tabs and their corresponding worksheets:

- Inventory Caps tab
 - Inventory Caps Worksheet (SKU/Store/Day)
- Inventory Capping Parameters tab
 - Inventory Caps Worksheet (SKU)
 - Inventory Caps Worksheet (Dept/Store/Day)


Note: Today must be included in the workbook.

Available Departments

The dialog box for Available Departments displayed below will show a list of all Departments. The user's previous selections are already selected. When a department(s) is selected by the user, all SKUs in the department(s) with a Capping Flag set to "Y" will automatically be included the workbook. The wizard will filter out SKUs with a Capping Flag set to "N".

If there are no SKUs with Capping Flag = Y, then a warning message "No capped SKUs available, please setup capped SKUS" will be displayed and the wizard will not be invoked. Once the user selects OK, the system will return to its base state.


There is no selection of individual SKUs through the wizard. The user has the ability to reselect which Departments will be accessed in the workbook. The positions default to the Department level. Standard RPAS functionality is available for this particular wizard page.



SRP Inventory Capping Management Wizard – Available Departments

Available Stores


The dialog box for Available Stores displayed below will show a list of all Stores in the AIP domain. The user's previous selections are already selected. The user has the ability to reselect which Stores will be accessed in the workbook. The positions default to the Store level. Standard RPAS functionality is available for this particular wizard page.



SRP Inventory Capping Management Wizard – Available Stores

Available Days

The dialog box for Available Days displayed below will show a list of all dates in the AIP domain. The user's previous selections are already selected. The user has the ability to reselect which dates will be accessed in the workbook. The positions default to the Day level. Standard RPAS functionality is available for this particular wizard page.



SRP Inventory Capping Management Wizard – Available Days

Inventory Caps Tab

Inventory Caps (SKU/Store/Day) Worksheet

The Inventory SKU Caps (SKU/Store/Day) Worksheet is used to manage SKU Caps by entering and accepting SKU Cap freezes, or accepting active SKU Caps, Working SKU Caps or System SKU Caps.

Location	Calendar	Measure	Active SKU Cap (Units)	Cap Type	SKU Cap Freeze (Units)
S1000000001 - Minneapolis	03/31/06				
100035032 - MONITOR,CRT,A91F+, ULT			3.00	Accept Prev	0.00
100036035 - DUMMY_PROJECTOR,PJ55'			2.00	Accept Prev	2.00
100037020 - PROJECTOR VIEWSONIC P			3.00	Accept Prev	0.00
100044001 - MONITOR,VA521,15",LCD I			1.00	Accept Prev	0.00
100045003 - MONITOR,ULTRA BRIGHT,1			2.00	Accept Prev	0.00
100045011 - MONITOR,VA721 17" LCD,'			3.00	Accept Prev	3.00
100045020 - MONITOR,VX710 17" LCD,'			3.00	Accept Prev	0.00
100046006 - MONITOR,VX910 19" LCD,'			2.00	Accept Prev	0.00
100049004 - AIP MONITOR,ULTRA BRIG			4.00	Accept Prev	4.00
100050013 - AIP DUMMY_PROJECTOR,P			3.00	Accept Prev	0.00

Inventory Caps (SKU/Store/Day) Worksheet

Once the department capacity and basic SKU Cap parameters are set, the user can review and modify SKU Caps using current information. The Inventory Caps worksheet provides the user with related information to assist in analyzing the SKU Cap data, such as forecast summed over the inventory capping forecast days and projected inventory. Department Capacity, SKU Capping Flag, and Relative Space per Unit are also available to be viewed in their respective worksheets while working in the SKU Caps worksheet.

Four views of the SKU caps are available to assist in the user analysis:

- The Active SKU cap is displayed, showing the values last committed in the workbook.
- The System SKU Caps displayed represent the SKU caps recommended by the system based on the inventory cap forecast and department capacity. The system caps are calculated each time the workbook is opened, giving the user a view of the caps using the latest forecast information. The user can enter "freeze" values for a SKU Cap to "lock" the cap at the value entered.
- The Working SKU Caps displayed represents the recommended SKU caps with the effects of any SKU cap freezes. The working caps are calculated each time the workbook is opened, using any committed freezes and the latest forecast data.
- The What-If SKU Caps display the cap values with the active, system, or working caps applied based on the cap type.

The user can enter "freeze" values for a SKU Cap to "lock" the cap at the value entered.

This worksheet contains the following measures:

Measure Label	Explanation
Active SKU Cap (Units) (expanded)	The Active SKU Cap (Units) represents the SKU Cap value in units that is currently being used in store replenishment plan calculations. During replenishment calculations, this is the maximum boundary for inventory at the store. This measure is read from the data base and expanded across time through the end of the workbook during the workbook build. This is a display only measure and will be populated with the What-If SKU Caps when “Apply Caps” is selected from the Menu button on the toolbar. Additionally, this measure will only be updated in the database when the caps have been applied and committed. (Read only)
Cap Type	The Cap Type is used to determine which caps will be used as the Active SKU Caps. The valid values for Cap Type are: ▪ Accept Active Cap If Cap Type is Accept Active Cap, the value in the active cap will become the What-If Cap for that SKU. ▪ Accept System Cap If Cap Type is Accept System Cap, the value in the system cap (not accounting for freezes) will become the What-If Cap for that SKU. ▪ Accept Working Cap If Cap Type is Accept Working Cap the value in the working cap (system cap with freezes factored in) will become the What-If Cap for that SKU. ▪ Accept Previous What-If The default value for the Cap Type is Accept Previous What-If. If Cap Type is Accept What-If Previous, the value in the What-If cap will become the previous day’s What-If Cap for that SKU. Since Cap Type is time-phased, Accept What-If Previous is necessary to preserve the What-If SKU Cap values selected. For example, if the user selects Accept System and calculates, the What-If SKU Cap will equal the system calculated caps on that day. If the default Cap Type was “Accept Active”, the What-If Caps for the subsequent days in the workbook would be equal to the Active Caps. If the Cap Type was “Accept System” for the remaining days, the What-If would equal to the System Caps calculated on each subsequent day. Having Accept What-If Previous as the default, the What-If SKU Caps will only change if Cap Type is changed by the user. Previous What-If is equal to the Active Cap upon opening the workbook.

Measure Label	Explanation
Inventory Cap Forecast	The Inventory Cap Forecast represents the forecast used in calculating the System SKU caps. Inventory Cap Forecast is calculated as the current forecasted demand summed over the Inventory Capping Forecast Days. Inventory Cap Forecast is used in the calculation of the system recommended SKU caps. The SKU's forecast is compared to the department's forecast to determine the portion of department capacity to be allocated to this SKU. Example: On the same day, in the same workbook with the Inventory Capping Forecast Days set to 7: The inventory cap forecast on 1/1/07 will be the sum of forecasts starting on 1/1/07 up to and including the forecast on 1/7/07. The inventory cap forecast on 3/1/07 will be the sum of forecasts starting on 3/1/07 up to and including the forecast on 3/7/07. (Read only)
SKU Cap Freeze (Units)	The SKU Cap Freeze (Units) measure that allows the user to override and freeze existing SKU Caps (Units) for Working SKU Cap calculations. Freezes can be used for various reasons, such as when a product is unavailable, to free up space for other products, or in situations when more space is needed for promotions or seasonal items. A SKU Cap Freeze essentially "locks" the cap at the value entered by the user. When a freeze is entered and Calculate selected, the Working SKU Caps are recalculated, distributing the remaining space across SKUs without freeze values. The freeze must be an integer greater than or equal to zero. Zero is a valid freeze value, indicating that no space is allocated for this SKU. If the freeze value entered by the user is greater than zero, it must have a minimum value equal to the SKU Pack Size. If the value is greater than zero and less than the SKU Pack Size, the freeze value remains the same. However, the working cap will be rounded up to one pack-size. Example: If the user enters a value of "2" (for a pack size of 4), the value displayed will be "2", while the value applied in calculations will be 4. The SKU Cap Freeze is entered in the workbook for the date it becomes effective. That freeze will remain in effect until the date where a new freeze is entered. To remove a freeze, a "-2" is entered for the freeze. Once calculate is selected, the entered freeze value will be spread across time in the SKU Cap Freeze (Units) Expanded measure. The SKU Cap Freeze (Units) Expanded value will be used in the calculating the Working SKU Caps. Note: A freeze can be committed to the data base at any time. The Active SKU Caps will only be modified when What-If caps are applied and committed.
SKU Cap Freeze (Units) (expanded)	The SKU Cap Freeze (Units) (Expanded) represents the SKU Cap Freeze values expanded across time through the end of the workbook. (Read only)
Store Ordering Pack Size	This value represents the ordering pack size for this store. This measure can be used to help define the Relative Space per Unit and Freeze values. (Read only)

Measure Label	Explanation
Store Projected Inventory	The Projected Inventory displays the original projected inventory from the last batch run. This measure is not used in any cap calculations.
System SKU Caps (Units)	The System SKU Cap (Units) represents the SKU Cap value in units calculated based on the SKU's forecast over Inventory Capping Forecast Days compared to the forecast over the same number of days for all capped SKUs within the department. The System SKU Caps show recommendations based on the latest forecasting data. In general, these caps are the basis for user analysis. Freezes are then made based on the user's knowledge but not factored into the calculation of the System SKU Cap. (Read only)
What-If SKU Cap (Space)	The What-If SKU Cap (Space) represents the relative space value of the SKU Cap. This is a display only measure calculated as the What-If SKU Cap (Units) * Relative Space per Unit. (Read only)
What-If SKU Cap (Units)	The What-If SKU Cap (Units) represents the SKU Cap value in units with the active, system, or working caps applied based on the cap type. When calculate is selected, the What-If caps are populated with the active, system, or working SKU caps selected (using cap type) and a check is done to see if the caps exceed department capacity. If department capacity is exceeded, a warning message is issued. If all CapTypes for a SKU/Store are 'Previous What-if', then the What-If = Active for every single day. If even one Cap Type for a SKU/Store is different from 'Previous What-if' then the What-If value would follow the Cap-Type setting. This is a calculated, display only measure not stored on the database. (Read only)
Working SKU Caps (Units)	The Working SKU Cap (Units) represents the SKU Cap value in units calculated based on the SKU's forecast over Inventory Capping Forecast Days for all capped SKUs within the department respecting any SKU Cap Freezes. During the working cap calculation, the freeze values will not be changed. All other caps will be calculated based on the SKU's Inventory Cap Forecast compared to the Total Inventory Cap Forecast for the department less the forecast for the overridden SKUs. This is a display only measure calculated when the workbook is built or when Calculate is selected, for example, after entering freezes. The Working SKU Caps give the user an opportunity to make a change by entering a freeze value, selecting calculate, and reviewing the effect of the freeze on other SKU Caps within the department. (Read only)

Inventory Caps Parameters Tab

Inventory Caps (SKU) Worksheet

This is a display only worksheet containing the SKU level measures used to assist the user in cap management.

Inventory Caps (SKU)	
Product	100035032 - MONITOR,CRT,A91F+, ULTRA BRGH
Capping Flag (expanded)	Yes
Relative Space per Unit (expanded)	1.00
Relative Space per Unit Status	Ok
Measure	

Inventory Caps (SKU) Worksheet

This worksheet contains the following measures. All measures are read only.

Measure Label	Explanation
Capping Flag (expanded)	The expanded Capping Flag represents the combined version of the SubClass level and SKU level Capping Flag settings, where the SKU level setting is the exception while the SubClass level is the Default. The Capping Flag is used to determine if inventory caps apply to subclasses and SKUs. Valid values are "Y" (capped), "N" (not capped), or "Not Set".
Relative Space per Unit (expanded)	The expanded Relative Space per Unit represents the combined version of the SubClass level and SKU level "Relative Space Per Unit" settings, where the SKU level setting is the exception while the SubClass level is the Default. Relative Space per Unit represents the relative amount of space one unit of the SKU will occupy. For example, a washer = 1, a refrigerator =2, etc. Relative Space per Unit is display only on this worksheet.
Relative Space per Unit Status	Relative Space per Unit Status is used to display the error message, "The 'Relative Space per Unit' equals zero". The status is maintained by the system and is display only.

Inventory Caps (Dept/Store/Day) Worksheet

The Inventory Caps (Dept/Store/Day) Worksheet displays department capacity information.

	03/31/06	04/01/06	04/02/06	04/03/06
Department Capacity (expanded)	35.00	35.00	35.00	35.00
Department Capacity Status	Ok	Ok	Ok	Ok
What-If Department Cap	21.00	8.00	8.00	8.00

Inventory Caps (Dept/Store/Day) Worksheet

The Department Capacity Worksheet contains the following three measures. All measures are read only.

Measure Label	Explanation
Department Capacity (Expanded)	The Department Capacity (Expanded) represents the capacity in a store for this department.
Department Capacity Status	Department Capacity Status is used to display the error message "The 'Department Capacity' has been exceeded". The status is maintained by the system and is display only.
What-If Department Cap	The What-If Department Cap represents the sum of all What-If SKU Caps (Space) for this department. What-If SKU Caps (Space) are calculated as the What-If SKU Caps (Units) multiplied by the corresponding Relative Space per Unit

SRP Apply Inventory Capping Workbook

The SRP Apply Inventory Capping Workbook is required to physically update the caps selected in the Inventory Cap Management workbook. This workbook is identical to the Inventory Cap Management workbook, with all the same capabilities and worksheets available.

Additionally, this workbook has the capability to apply the caps using the Inventory Capping menu button and update the database. This workbook gives the ability to restrict the number of users who can update the caps using RPAS security.

Apply SKU Cap

The Apply SKU Cap option, available from the Apply SKU Cap menu, provides the user with the means to update the database with the desired cap values.

Selecting Apply SKU Caps populates the Active SKU Caps values on the worksheet with the What-If SKU caps and all Cap Types are set back to the default value of "Previous What-If".

SRP Presentation Stock Calculations Workbook

The SRP Presentation Stock Calculations workbook allows users to analyze the inputs to the Store Presentation Stock calculation. The user also has the opportunity to edit the exception level parameter measures. This workbook contains one tab and its corresponding worksheet:

- Store Presentation Stock Calculations (SKU/Store/Day) Tab
 - Store Presentation Stock Calculations (SKU/Store/Day) Worksheet

The workbook is global domain enabled.


Note: Today and Yesterday must be included in the workbook.

SRP Store Presentation Stock Calculations Wizard

Available SKUs

The dialog box for Available SKUs will show a list of all active SKUs in the AIP domain. A SKU is considered active if, for at least one SKU pack size at a particular destination, the lead time is ≥ 0 for any source on any day within the scheduled horizon.


Any previous selections will still be selected, and the user has the ability to reselect which SKUs will be accessed in the workbook. The displayed positions will default to the SKU level. Standard RPAS functionality is available for this particular wizard page.



SRP Presentation Stock Calculations Wizard – Available SKUs

Available Stores

The Available Stores wizard screen displays a list of all Stores in the AIP domain. Any previous selections will still be selected, and the user has the ability to reselect which Stores will be accessed in the workbook. The displayed positions will default to the Store level. Standard RPAS functionality is available for this particular wizard page.



SRP Presentation Stock Calculations Wizard – Available Stores

Available Days

The Available Days wizard screen displays a list of all Days in the AIP domain. Any previous selections will still be selected, and the user has the ability to reselect which Days will be accessed in the workbook. The displayed positions will default to the Days level. If multiple days are selected, they must be consecutive days and must include today and yesterday. Standard RPAS functionality is available for this particular wizard page.

When you select **Finish**, the workbook will be built using the SKUs, Stores, and Days selected.

Note: Historical values in this workbook cannot be edited; thus, all historical measure values (i.e., those values before and including “today”) are read-only. Edits are only permitted for measure values after “today” through the planning horizon displayed in the worksheet. “Today” is also read-only.

The screenshot displays the 'SRP Presentation Stock Calculations Wizard' window, specifically the 'Available Days' tab. The window is divided into two main sections: 'Available Days' on the left and 'Selected Days' on the right. The 'Available Days' list contains dates from 04/01/06 to 04/24/06. The first 14 dates (04/01/06 through 04/14/06) are marked with red checkmarks, indicating they are selected. The 'Selected Days' list on the right also contains these 14 dates. Below the 'Available Days' list is a checkbox labeled 'Synchronize hierarchies' which is currently unchecked. At the bottom of the window are five buttons: 'Cancel', '<Back', 'Next>', 'Finish', and 'Help'.

SRP Presentation Stock Calculations Wizard – Available Days

Store Presentation Stock Calculations (SKU/Store/Day) Tab

	04/01/06	04/02/06	04/03/06	04/04/06
Base Store Promotion Presentation Stock	0.00	0.00	0.00	0.00
Calculated Store Presentation Stock	0.00	0.00	0.00	0.00
End of Store Promotion Factor (expanded)	1.00	1.00	1.00	1.00
Store Minimum Presentation Stock				
Store Minimum Presentation Stock (expanded)	0.00	0.00	0.00	0.00
Store Presentation Stock	0.00	0.00	0.00	0.00
Store Presentation Stock Override Flag				
Store Presentation Stock Override Flag (expanded)	Off	Off	Off	Off
Store Presentation Stock Override Quantity				
Store Presentation Stock Override Quantity (expanded)	0.00	0.00	0.00	0.00
Store Promotion Presentation Stock	0.00	0.00	0.00	0.00
Store Promotion Presentation Stock Override Flag				
Store Promotion Presentation Stock Override Flag (expanded)	Off	Off	Off	Off
Store Weekly Base Sales Forecast %				
Store Weekly Base Sales Forecast % (expanded)	0.00	0.00	0.00	0.00
User Specified Store Presentation Stock				
User Specified Store Presentation Stock (expanded)	0.00	0.00	0.00	0.00
Weekly Base Sales Forecast	0.00	0.00	0.00	0.00

Store Presentation Stock Calculations (SKU/Store/Day) Worksheet

Store Presentation Stock Calculations (SKU/Store/Day) Worksheet

The Store Presentation Stock (SKU/Store/Day) worksheet contains the inputs to the Store Presentation Stock calculation.

The following measures appear automatically when using the default template.

Measure Label	Description
Base Store Promotion Presentation Stock	The Base Store Promotion Presentation Stock represents the specified quantity for Store Promotion Presentation Stock before application of the End of Store Promotion Factor.
Calculated Store Presentation Stock	The Calculated Store Presentation Stock represents the maximum of the Weekly Base Sales Forecast multiplied by the Weekly Base Sales Forecast % and the Store Minimum Presentation Stock.
End of Store Promotion Factor (expanded)	The expanded version of End of Store Promotion Factor will display the actual value used in the calculations. This version will display a factor of 1 for the days within the promotion period prior to the ramp down and will then show the designated End of Promotion Factor values as it approaches the end of the promotion. A factor of 1 will be displayed after the promotion has ended
Store Minimum Presentation Stock	The Store Minimum Presentation Stock indicates the minimum presentation quantity to be used in the calculation of store presentation stock. Any value greater than or equal to zero ("0") is acceptable.

Measure Label	Description
Store Minimum Presentation Stock (expanded)	The expanded version of Store Minimum Presentation Stock, which displays the actual value used in calculations. This represents the merge of the global default, default, and exception level versions of Store Minimum Presentation Stock.
Store Presentation Stock	The Store Presentation Stock represents the maximum of the Calculated Store Presentation Stock and the User Specified Store Presentation Stock. If the Calculated Store Presentation Stock Indicator is turned off, "0" is used in place of the Calculated Store Presentation Stock in this calculation.
Store Presentation Stock Override Flag	The Store Presentation Stock Override Flag is used when calculating the Store Presentation Stock to indicate whether the override quantity should be used. When the Store Global Default Presentation Stock Override Flag is turned on ("TRUE"), the override quantity should be used.
Store Presentation Stock Override Flag (expanded)	The expanded version of Store Presentation Stock Override Flag, which displays the actual value used in calculations. This represents the merge of the global default, default, and exception level versions of Store Presentation Stock Override Flag.
Store Presentation Stock Override Quantity	The Store Presentation Stock Override Quantity is the value used when calculating Store Presentation Stock if the override flag is turned on ("TRUE").
Store Presentation Stock Override Quantity (expanded)	The expanded version of Store Presentation Stock Override Quantity, which displays the actual value used in calculations. This represents the merge of the global default, default, and exception level versions of Store Presentation Stock Override Quantity.
Store Promotion Presentation Stock	The Store Promotion Presentation Stock represents the End of Store Promotion Factor applied to the Base Store Promotion Presentation Stock. If the Store Promotion Presentation Stock Override Flag is turned on, this becomes equal to zero ("0").
Store Promotion Presentation Stock Override Flag	The Store Promotion Presentation Stock Override Flag indicates what value should be used for Store Promotion Presentation Stock. When the override flag is turned on ("TRUE"), the Store Promotion Presentation Stock equals zero ("0").
Store Promotion Presentation Stock Override Flag (expanded)	The expanded version of Store Promotion Presentation Stock Override Flag will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered.
Store Weekly Base Sales Forecast %	The Store Weekly Base Sales Forecast indicates what percentage of the Weekly Base Sales Forecast should be used in the calculation of store presentation stock. Values between 0 and 1 (inclusive) are valid. Zero ("0") indicates that 0% of the forecast should be used and "1" indicates that 100% of the forecast should be used.

Measure Label	Description
Store Weekly Base Sales Forecast % (expanded)	The expanded version of Store Weekly Base Sales Forecast, which displays the actual value used in calculations. This represents the merge of the global default, default and exception level versions of Store Weekly Base Sales Forecast. Zero ("0") indicates that 0% of the forecast should be used and "1" indicates that 100% of the forecast should be used.
User Specified Store Presentation Stock	The User Specified Store Presentation Stock represents the minimum amount of stock in UNITS desired to have on hand for display/sales purposes. User Specified Store Presentation Stock may be taken into consideration when calculating the Receipt Point and Receive up to Level, depending on the Boundary Stock selected.
User Specified Store Presentation Stock (expanded)	The expanded version of User Specified Store Presentation Stock will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered.
Weekly Base Sales Forecast	The Weekly Base Sales Forecast is the day level representation of the weekly base sales forecast. This is calculated by replicating the value from Loaded Weekly Base Sales Forecast to sku/str/day.

USA Workbooks

The allocation of product to store locations is a critical component of the merchandising supply chain that affects customer service, inventory costs, sales and turn over goals, and profitability. SRP provides you with functionality to support User Specified Allocations (USAs).

User Specified Allocations allow users to make adjustments to inventory flow by:

- Reviewing and revising order quantities at an aggregate or individual location/SKU level
- Adding to or replacing store replenishment plans
- Using projected inventory to plan future allocations
- Using rule-based methods
- Providing a “Delivery Window,” which lessens the strain on distribution by giving DC a delivery window
- Triggering POs to be launched to suppliers by Warehouse Replenishment Planning or for Direct to Store when needed

There are four types of User Specified Allocations:


- Replacement
- Additive
- Delivery window
- Allocation on index (AOI), which is a rule-based allocation

USAs are typically used to manage the following types of business events:

- Clearances, which push stock from the warehouses to the stores
- Seasonal SKUs, which are affected by seasonal changes, such as weather-related product like ice scrapers and snow blowers
- Known limited supply (drip-feeding the stores with the product)
- New stores/reinvigorated stores
- Sampling
- Disaster management
- Delivery window allocation, which are initial allocations of seasonal products like Christmas Cookies
- Forecasting is not possible or accurate
- Product launch, which refers to filling up stores with stock that is based on display needs

Planning and Allocation are not two independent processes in AIP. Store Planning incorporates the allocation process directly into the planning process by adding to or replacing the planned order that is generated with the User Specified Allocation. USAs give you the ability to review and revise the allocation prior to approving it. This functionality allows for revisions at an aggregate level or at an individual SKU/location level and review by chosen attributes prior to approval.

The USA process is as follows:



USA Business Process Flow

USA Business Process

Create USA workbook – Select the type of USA that you want to perform (Replacement, Top Up, Delivery Window, or AOI) and walk through a series of wizards that provide SRP with the additional data it needs in order to build the USA workbook.

Setup user-specified allocation – Through the USA workbook, enter the quantity that you want to allocate (either by store or by source).

Commit modified allocations – Once the quantities have been entered and modified based on factors like pack size or AOI, review the final store-level impact of the USA and commit the modified allocation.

Incorporate USAs into the store replenishment plan – Once a USA is committed, its values become available to AIP to incorporate the USA into the store plan by modifying the replenishment boundaries so they account for the newly allocated quantities.

There are seven User Specified Allocation workbooks in SRP:

- USA Replacement, Additive and Delivery Window Workbook
- USA Allocation on Dynamic Rule Based Index Workbook
- USA Allocation on Rule Based Index Workbook
- USA Allocation on Store Based Index Workbook
- USA Create Rule Based Index Workbook
- USA Create Store Based Index Workbook
- USA Delete Workbook

USA Replacement, Additive, and Delivery Window Workbook

The USA Replacement, Additive, and Delivery Window workbook allows the user to set up a Replacement USA, and Additive USA and/or a Delivery Window USA. USAs can be created at any time before the order is released to the source stocking point for execution. This allows the user to enter the USA for any day in the future within the planning horizon.

A Replacement USA overrides the planned store order. It is used when a user judges that store calculated orders would not meet business requirements. One key example is for a popular seasonal product with limited stock, which needs to be ‘drip-fed’ into the stores, rather than be ordered by the store’s calculation against normal customer demand, which would lead to a long-term stock-out well before the end of the season.

An Additive USA adds the USA quantity to the store order. An Additive USA is used when a user judges that store's calculated orders would not completely meet business requirements. Additive USAs are used when the user believes that the forecasts are generally correct but that for some certain store(s) additional stock may need to be pushed through the supply chain from the source stocking point.

A Delivery Window USA is a replacement type USA. The difference from the Fixed Replacement USA is that the user specifies the receive-by date rather than the receive-on date and the delivery window over which that commodity can be delivered. A Delivery Window USA can only be made for those items being sourced to a store by a warehouse only.

This workbook contains three worksheets that are grouped into a single tab:

- USA Replacement, Additive and Delivery Window tab
 - Store Level Information Worksheet
 - Warehouse Level Information Worksheet
 - Supplier Level Information Worksheet

USA Replacement, Additive, and Delivery Window Wizard

Available Receive On Days

Available Receive On Days displays a list of all dates from tomorrow through the maximum planning horizon. Only one Selected Receive On Day is allowed. The user's previous selection is not already selected. The user has the ability to select which date will be accessed in the workbook. Standard RPAS functionality is available for this wizard page.

The screenshot shows a Windows-style dialog box titled "USA Replacement, Additive and Delivery Window Wizard". It has a blue title bar with a close button (X) in the top right corner. The main area is divided into two panes. The left pane, titled "Available Receive on Days", contains a list of dates from 04/02/06 to 04/15/06. The date 04/03/06 is selected, indicated by a red checkmark and a dashed border. Below this list is a checkbox labeled "Synchronize hierarchies" which is currently unchecked. The right pane, titled "Selected Receive on Day", contains a single entry: 04/03/06. At the bottom of the dialog are five buttons: "Cancel", "<Back", "Next>", "Finish", and "Help".


USA Replacement, Additive, and Delivery Window Wizard – Available Receive on Days

Available SKUs

The dialog box for Available SKUs wizard screen displays a list of all SKUs that


- Have a Source for the store on the day selected
- Are On Supply for any store on either the day selected or any date within the planning horizon
- Have a valid Store Ordering Pack Size on the day selected

The user's previous selections are not already selected. The user has the ability to select which SKUs will be accessed in the workbook. Standard RPAS functionality is available for this wizard page.




USA Replacement, Additive, and Delivery Window Wizard – Available SKUs

If no filtering criteria were met for any SKU based on the receive-on date selected from the previous wizard screen, the user will be notified by the following warning message:



Available Source Stocking Points

The Available Source Stocking Points wizard screen displays a list of all Source Stocking Points for the SKUs and day selected. The user's previous selections are not already selected. The user has the ability to select which Source Stocking Points will be accessed in the workbook. Standard RPAS functionality is available for this wizard page.




USA Replacement, Additive, and Delivery Window Wizard – Available Source Stocking Points

Note: If no warehouse stocking point is selected, the first warehouse found is brought into the workbook. If no supplier stocking point is selected, the first supplier found is brought into the workbook. Also, Delivery Window USAs can only be created for those items sourced by a warehouse.

Available Stores

The dialog box for Available Stores wizard screen displays a list of all Stores sourced by the selected Source Stocking Point for the SKUs and day selected and the SKU is On Supply.

The user's previous selections are not already selected. The user has the ability to select which Stores will be accessed in the workbook. Standard RPAS functionality is available for this wizard page.



USA Replacement, Additive, and Delivery Window Wizard – Available Stores

Click Finish to build the workbook using the selected criteria.

USA Replacement, Additive and Delivery Window Tab

Store Level Information Worksheet

The Store Level Information worksheet displays store specific pack size, cases per pallet, and source level information. This worksheet allows the user to create or update USAs at the SKU/Store/Day level. The allocation type is specified and the USA can be entered in units or packs.

Product	Location	Calendar
100035008 - CALCULATOR, GRAPHIC	S303 - MISHAWA	04/03/06
Cases Per Pallet	0	
Store Allocation Type	None	
Store Delivery Window	0	
Store Ordering Pack Size	1.00	
Store Percent of Pallet (expanded)	0.00	
Store Source Label	W1090 - MIP	
Store User Specified Allocation		
USA Number of packs per store		

Store Level Information Worksheet

The following measures are displayed automatically when using the default template.

Measure Label	Description
Cases Per Pallet	Cases Per Pallet reflects the number of cases on a pallet. Note: Cases Per Pallet is loaded from Data Management online (DMo). (Read only)
Store Allocation Type	The Store Allocation Type indicates whether the allocation should be added to the receipt plan calculation or whether it should act as a replacement of the receipt plan. Upon opening the workbook, the Store Allocation Type will display "unavailable" for any invalid combinations (no store source, not on supply, or invalid store ordering packsize). If a USA was deleted previously and the date it was deleted is still after today, the workbook will display 0 units for the USA and None as the Allocation Type. This will give the user the opportunity to create a USA even though it was deleted previously. If the Allocation Type is not "unavailable", Valid values are: - None - Add - Replace - Delivery Window Note: Delivery Window USAs can only be set up for those SKU/Store combinations sourced by a warehouse.

Measure Label	Description
Store Delivery Window	The Store Delivery Window indicates the time window over which the Delivery Window allocation quantity has to be delivered from the warehouse to the stores. If the delivery window entered put the release date before today, the delivery window is changed back to its original value and the following alert is issued: “The Release Date is before today. Please refresh the workbook and enter a smaller delivery window.” At this point the workbook is unstable, and must be refreshed before continuing. The Store Delivery Window is only updated in the database if the Allocation type is ‘Delivery Window’.
Store Ordering Pack Size	The Store Ordering Pack Size represents the primary pack size to be used when ordering a SKU for a store (either from a warehouse or from a supplier). Note: Store Ordering Pack Size is loaded from Data Management online (DMo). The allocation must be a multiple of the store ordering pack size (Read only)
Store Percent of Pallet (expanded)	Percent of pallet is used to determine if the Ideal Receipt Quantity for replenishment should be rounded to a full pallet. It represents the percentage threshold that case demand must exceed in order for pallet rounding to occur. The expanded version of Store Percent of Pallet will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered. (Read only)
Store Source Label	The Store Source Label identifies the source from which this store receives inventory. (Read only)
Store User Specified Allocation	The Store User Specified Allocation represents the number of units to replace or add to an unreleased store order. Any positive integer, including zero, is valid. If the number entered is not a multiple of the Store Ordering Pack Size, it is rounded to the nearest Store Ordering Pack Size based on the Store Rounding Threshold. If the Store Allocation Type is Add, the value is added to the store order. If the Store Allocation Type is Replace, the value replaces the store order. If the Store Allocation Type is Delivery Window, the value replaces the store order. If the “USA Number of packs per store” changes, the USA is calculated as the USA Number of packs per store multiplied by the Store Ordering Packsize. The Store User Specified Allocation is only updated in the database if the Allocation type is “Add”, “Replace” or “Delivery Window”.

Measure Label	Description
USA Number of packs per store	The USA Number of packs per store allows the user to specify the USA in packs. When the number of packs is specified, the Store User Specified Allocation will be updated to reflect the number in units. Any positive integer, including zero, is valid. If the “Store User Specified Allocation” changes, the USA Number of packs per store is calculated as the Store User Specified Allocation divided by the USA Number of packs per store.

Warehouse Level Information Worksheet

The Warehouse Level Information worksheet displays the release date, cases per pallet, and warehouse inventory information. Updates made at the warehouse level are spread back to the store level.

Warehouse Level Information Worksheet

The following measures are displayed automatically when using the default template.

Measure Label	Description
USA Average Delivery Window by Store	The USA Average Delivery Window by Store is the average of the sum of Store Delivery Window of this SKU for all stores in the workbook sourced by this warehouse. Any positive integer, including zero, is valid. If the average delivery window is updated, the value entered is replicated for all stores in the workbook sourced by this warehouse. If the average delivery window entered put the release date before today, the delivery window is changed back to its original value and an alert is issued. At this point the workbook is unstable, and must be refreshed before continuing.
USA Average WH Cases by Store	The USA Average WH Cases by Store is the average of the sum of Average WH Cases by Store of this SKU for all stores in the workbook sourced by this warehouse. Any positive integer, including zero, is valid. If the average WH cases value is updated, the value entered is replicated for all stores in the workbook sourced by this warehouse.

Measure Label	Description
USA Average WH Units by Store	The USA Average WH Units by Store is the average of the sum of Average WH Units by Store of this SKU for all stores in the workbook sourced by this warehouse. Any positive integer, including zero, is valid. If the average WH units value is updated, the value entered is replicated for all stores in the workbook sourced by this warehouse.
USA Earliest WH Release Date by Store	The USA Earliest WH Release Date by Store is calculated based on the maximum lead time for the stores sourced by this warehouse. For Delivery Window USAs, the earliest release date is the greater of the lead time and delivery window for the stores sourced by this warehouse. If the Release Date is aggregated to a higher level, the value of the earliest release date is displayed. (Read only)
USA Total Allocated WH Cases by Store	The USA Total Allocated WH Cases by Store is the total of the USA Number of packs per store of this SKU for all stores in the workbook sourced by this warehouse. (Read only)
USA Total Allocated WH Units by Store	The USA Total Allocated WH Units by Store is the total of the Store User Specified Allocation of this SKU for all stores in the workbook sourced by this warehouse. (Read only)
USA Warehouse Allocation Type	The USA Warehouse Allocation Type is the allocation type of this SKU for all stores in the workbook sourced by this warehouse. If the values are different, a question mark (?) will be displayed. If the Allocation Type is not “unavailable”, Valid values are: ▪ None ▪ Add ▪ Replace ▪ Delivery Window If the user updates the Warehouse Allocation Type of this SKU, it is replicated for all stores in the workbook sourced by this warehouse.
USA WH Percent of Pallet	The USA WH Percent of Pallet is percent of pallet of this SKU for all stores in the workbook sourced by this warehouse. . If the values are different, a question mark (?) will be displayed. (Read only)
USA WH Projected Inventory	USA WH Projected Inventory represents the total projected inventory of this SKU shifted by lead time at the source warehouse. The day the projected inventory is shown for each SKU corresponds to the earliest warehouse release day when there are multiple release days for a single receipt date at any of the stores (in other words, corresponding to the max lead time). (Read only)

Supplier Level Information Worksheet

The Supplier Level Information worksheet displays the release date, average unit and cases by supplier. Updates made at the supplier level are spread back to the store level.

Measure	Value
USA Average Supplier Cases by Store	0
USA Average Supplier Units by Store	0.00
USA Earliest Supplier Release Date by Store	4/3/2006
USA Supplier Allocation Type	None
USA Total Allocated Supplier Cases by Store	0
USA Total Allocated Supplier Units by Store	0.00

Supplier Level Information Worksheet

The following measures are displayed automatically when using the default template.

Measure Label	Description
USA Average Supplier Cases by Store	The USA Average Supplier Cases by Store is the average of the sum of Average Supplier Cases by Store of this SKU for all stores in the workbook sourced by this supplier. Any positive integer, including zero, is valid. If the average Supplier cases value is updated, the value entered is replicated for all stores in the workbook sourced by this supplier.
USA Average Supplier Units by Store	The USA Average Supplier Units by Store is the average of the sum of Average Supplier Units by Store of this SKU for all stores in the workbook sourced by this supplier. Any positive integer, including zero, is valid. If the average Supplier units is updated, the value entered is replicated for all stores in the workbook sourced by this supplier.
USA Earliest Supplier Release Date by Store	The USA Earliest Supplier Release Date by Store is calculated based on the maximum lead time for the stores sourced by this supplier. For Delivery Window USAs, the earliest release date is the greater of the lead time and delivery window for the stores sourced by this supplier. If the Release Date is aggregated to a higher level, the value of the earliest release date is displayed. (Read only)
USA Supplier Allocation Type	The USA Supplier Allocation Type is the allocation type of this SKU for all stores in the workbook sourced by this supplier. If the values are different, a "?" will be displayed. If the Allocation Type is not "unavailable", Valid values are: - None - Add - Replace - Delivery Window If the user updates the Supplier Allocation Type of this SKU, it is replicated for all stores in the workbook sourced by this supplier.

Measure Label	Description
USA Total Allocated Supplier Cases by Store	The USA Total Allocated Supplier Cases by Store is the total of the USA Number of packs per store of this SKU for all stores in the workbook sourced by this supplier. (Read only)
USA Total Allocated Supplier Units by Store	The USA Total Allocated Supplier Units by Store is the total of the Store User Specified Allocation of this SKU for all stores in the workbook sourced by this supplier. (Read only)

USA Allocation on Dynamic Rule Based Index Workbook

The USA Allocation on Dynamic Rule Based Index workbook allows the user to specify a quantity from the source stocking point to spread proportionally across a set of stores taking into account the store inventory. The ratio for this spread is based on one of three rules: Store Adjusted Sales, Store Demand Forecast or Store Receipt Plan. A Watershed Algorithm is used in the allocation of these quantities to the store level.

This workbook contains three worksheets that are grouped into a single tab:

- USA Allocation on Dynamic Rule Based Index tab
 - Store Level Information Worksheet
 - Warehouse Level Information Worksheet
 - Supplier Level Information Worksheet

USA Allocation on Dynamic Rule Based Index Workbook Wizard

Available Receive On Days

Available Receive On Days displays a list of all dates from tomorrow through the maximum planning horizon. Only one Selected Receive On Day is allowed. The user's previous selection is not already selected. The user has the ability to select which date will be accessed in the workbook. Standard RPAS functionality is available for this wizard page.

The screenshot shows a wizard window titled "USA Allocation on Dynamic Rule Based Index Wizard". It has two tabs: "Available Receive on Days" and "Position Query Definitions".

Under the "Available Receive on Days" tab, there is a list of dates from 04/02/06 to 04/15/06. The date 04/03/06 is selected with a red checkmark. Below the list is a checkbox labeled "Synchronize hierarchies" which is unchecked.

Under the "Position Query Definitions" tab, there is a list containing the selected date 04/03/06.

At the bottom of the window are five buttons: "Cancel", "<Back", "Next>", "Finish", and "Help".


USA Allocation on Dynamic Rule Based Index Workbook Wizard – Available Receive on Days

Available SKUs

The dialog box for Available SKUs wizard screen displays a list of all SKUs that


- Have a Source for the store on the day selected
- Are On Supply for any store on either the day selected or any date within the planning horizon
- Have a valid Store Ordering Pack Size on the day selected

The user's previous selections are not already selected. The user has the ability to select which SKUs will be accessed in the workbook. Standard RPAS functionality is available for this wizard page.




USA Allocation on Dynamic Rule Based Index Workbook Wizard – Available SKUs

If no filtering criteria were met for any SKU based on the receive-on date selected from the previous wizard screen, the user will be notified by the following warning message:



Available Source Stocking Points

The Available Source Stocking Points wizard screen displays a list of all Source Stocking Points for the SKUs and day selected. The user's previous selections are not already selected. The user has the ability to select which Source Stocking Points will be accessed in the workbook. Standard RPAS functionality is available for this wizard page.




USA Allocation on Dynamic Rule Based Index Workbook Wizard – Available Source Stocking Points

Note: If no warehouse stocking point is selected, the first warehouse found is brought into the workbook. If no supplier stocking point is selected, the first supplier found is brought into the workbook. Also, Delivery Window USAs can only be created for those items sourced by a warehouse.

Available Stores

The dialog box for Available Stores wizard screen displays a list of all Stores sourced by the selected Source Stocking Point for the SKUs and day selected and the SKU is On Supply.

The user's previous selections are not already selected. The user has the ability to select which Stores will be accessed in the workbook. Standard RPAS functionality is available for this wizard page.




USA Allocation on Dynamic Rule Based Index Workbook Wizard – Available Stores

Please choose a rule

This dialog box allows the user to choose a rule from the following options:

- Store Adjusted Sales
- Store Receipt Plan
- Store Demand Forecast



USA Allocation on Dynamic Rule Based Index Workbook Wizard – Choose Rule

Available days to include in index calculation

The available days to include in the index calculations are selected based on the rule selected.

For Store Adjusted Sales, select days before today to include in the index calculation.

For Store Receipt Plan or Store Demand Forecast, select days after today to include in the index calculation.

In all cases the days selected must be consecutive days.

USA Allocation on Dynamic Rule Based Index Wizard

Available days to include in index calculation

- ☐ 03/14/06
- ☐ 03/15/06
- ☐ 03/16/06
- ☒ 03/17/06
- ☒ 03/18/06
- ☒ 03/19/06
- ☒ 03/20/06
- ☒ 03/21/06
- ☒ 03/22/06
- ☒ 03/23/06
- ☒ 03/24/06
- ☐ 03/25/06
- ☐ 03/26/06
- ☐ 03/27/06
- ☐ 03/28/06
- ☐ 03/29/06
- ☐ 03/30/06
- ☐ 03/31/06

☐ Synchronize hierarchies

Selected days

- 03/17/06
- 03/18/06
- 03/19/06
- 03/20/06
- 03/21/06
- 03/22/06
- 03/23/06
- 03/24/06

Position Query Definitions

Cancel <Back Next> Finish Help

USA Allocation on Dynamic Rule Based Index Workbook Wizard –Select Days to Build Index

Click Finish to build the workbook on the selected criteria.

USA Allocation on Dynamic Rule Based Index Tab

Store Level Information Worksheet

The Store Level Information worksheet displays the calculated USA quantity, AOI Index quantity, store specific pack size, cases per pallet, and source level information. It also provides the ability to enter maximum and minimum boundaries by SKU/store for the AOI quantity that is being pushed from the warehouse.

Store Level Information Worksheet

The following measures are displayed automatically when using the default template.

Measure Label	Description
Cases Per Pallet	Cases Per Pallet reflects the number of cases on a pallet. Note: Cases Per Pallet is loaded from Data Management online (DM). (Read only)
Store Allocation Type	The Store Allocation Type indicates whether the allocation should be added to the receipt plan calculation or whether it should act as a replacement of the receipt plan. Upon opening the workbook, the Store Allocation Type will display “unavailable” for any invalid combinations (no store source, not on supply, or invalid store ordering packsize). If the watershed calculation changes the allocation quantity, the Store User Specified Allocation is changed to “Replace”. (Read only)
Store Ordering Pack Size	The Store Ordering Pack Size represents the primary pack size to be used when ordering a SKU for a store (either from a warehouse or from a supplier). Note: Store Ordering Pack Size is loaded from Data Management online (DMo). The allocation must be a multiple of the store ordering pack size (Read only)

Measure Label	Description
Store Percent of Pallet (expanded)	Percent of pallet is used to determine if the Ideal Receipt Quantity for replenishment should be rounded to a full pallet. It represents the percentage threshold that case demand must exceed in order for pallet rounding to occur. The expanded version of Store Percent of Pallet will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered. (Read only)
Store Source Label	The Store Source Label identifies the source from which this store receives inventory. (Read only)
Store User Specified Allocation	The Store User Specified Allocation represents the number of units to replace or add to an unreleased store order. When the source stocking point units are allocated to the stores using the watershed, algorithm, the Store User Specified Allocation changes to reflect the number of units each store was allocated. Since the allocations must be rounded to packsize, the total allocation quantity from the source may not be met. The Store User Specified Allocation is only updated in the database if the Allocation type is "Replace". (Read only)
USA AOI Allocation Index	The USA AOI Allocation Index is calculated as the sum of the days selected to build the index. The watershed algorithm uses the index to determine the ratio for distributing the units across the stores. (Read only)
USA Maximum Shipping Units per store	The USA Maximum Shipping Units per store represents the maximum quantity that can be shipped to the store for this product. The Specified Allocation cannot exceed this value. Any positive integer, including zero, is valid. The USA Maximum Shipping Units per store is only updated in the database if the Allocation type is "Replace".
USA Minimum Shipping Units per store	The USA Minimum Shipping Units per store represents the minimum quantity that can be shipped to the store for this product. The Specified Allocation must be equal to or greater than this value. Any positive integer, including zero, is valid. The USA Minimum Shipping Units per store is only updated in the database if the Allocation type is "Replace".
USA Number of packs per store	When the "Store User Specified Allocation" value changes, the number of packs is calculated as the Store User Specified Allocation divided by the USA Number of packs per store. (Read only)

Warehouse Level Information Worksheet

The Warehouse Level Information worksheet provides the ability to push USAs based on an allocation index to stores. This worksheet displays the earliest release date and warehouse inventory information. It also provides the ability to enter warehouse allocation maximum and minimum boundaries and a total allocation quantity to be pushed to stores. This can either be in units or cases.

Product	Warehouse	Calendar
100035008 - CALCULATOR, GRAPHING, SI	W1090 - MI	
	04/03/06	
USA AOI WH Allocate by Store		
USA AOI WH Allocation Status by Store		
USA Earliest WH Release Date by Store	4/2/2006	
USA Total Allocated WH Cases by Store	0	
USA Total Allocated WH Units by Store	0.00	
USA WH Maximum Shipping Units	999999.00	
USA WH Minimum Shipping Units	0.00	
USA WH Percent of Pallet	0	
USA WH Projected Inventory	0.00	

Warehouse Level Information Worksheet

The following measures are displayed automatically when using the default template.

Measure Label	Description
Cases Per Pallet	Cases Per Pallet reflects the number of cases on a pallet. Note: Cases Per Pallet is loaded from Data Management online (DM). (Read only)
Store Allocation Type	The Store Allocation Type indicates whether the allocation should be added to the receipt plan calculation or whether it should act as a replacement of the receipt plan. Upon opening the workbook, the Store Allocation Type will display "unavailable" for any invalid combinations (no store source, not on supply, or invalid store ordering packsize). If the watershed calculation changes the allocation quantity, the Store User Specified Allocation is changed to "Replace". (Read only)
Store Ordering Pack Size	The Store Ordering Pack Size represents the primary pack size to be used when ordering a SKU for a store (either from a warehouse or from a supplier). Note: Store Ordering Pack Size is loaded from Data Management online (DMo). The allocation must be a multiple of the store ordering pack size (Read only)

Measure Label	Description
Store Percent of Pallet (expanded)	Percent of pallet is used to determine if the Ideal Receipt Quantity for replenishment should be rounded to a full pallet. It represents the percentage threshold that case demand must exceed in order for pallet rounding to occur. The expanded version of Store Percent of Pallet will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered. (Read only)
Store Source Label	The Store Source Label identifies the source from which this store receives inventory. (Read only)
Store User Specified Allocation	The Store User Specified Allocation represents the number of units to replace or add to an unreleased store order. When the source stocking point units are allocated to the stores using the watershed, algorithm, the Store User Specified Allocation changes to reflect the number of units each store was allocated. Since the allocations must be rounded to packsize, the total allocation quantity from the source may not be met. The Store User Specified Allocation is only updated in the database if the Allocation type is "Replace". (Read only)
USA AOI Allocation Index	The USA AOI Allocation Index is calculated as the sum of the days selected to build the index. The watershed algorithm uses the index to determine the ratio for distributing the units across the stores. (Read only)
USA Maximum Shipping Units per store	The USA Maximum Shipping Units per store represents the maximum quantity that can be shipped to the store for this product. The Specified Allocation cannot exceed this value. Any positive integer, including zero, is valid. The USA Maximum Shipping Units per store is only updated in the database if the Allocation type is "Replace".
USA Minimum Shipping Units per store	The USA Minimum Shipping Units per store represents the minimum quantity that can be shipped to the store for this product. The Specified Allocation must be equal to or greater than this value. Any positive integer, including zero, is valid. The USA Minimum Shipping Units per store is only updated in the database if the Allocation type is "Replace".
USA Number of packs per store	When the "Store User Specified Allocation" value changes, the number of packs is calculated as the Store User Specified Allocation divided by the USA Number of packs per store. (Read only)

Supplier Level Information Worksheet

The Supplier Level Information worksheet provides the ability to push USAs based on an allocation index to stores. This worksheet displays the earliest release date and provides the ability to enter supplier allocation maximum and minimum boundaries and a total allocation quantity to be pushed to stores. This can either be in units or cases.

Supplier Level Information Worksheet

The following measures are displayed automatically when using the default template.

Measure Label	Description
Cases Per Pallet	Cases Per Pallet reflects the number of cases on a pallet. Note: Cases Per Pallet is loaded from Data Management online (DM). (Read only)
Store Allocation Type	The Store Allocation Type indicates whether the allocation should be added to the receipt plan calculation or whether it should act as a replacement of the receipt plan. Upon opening the workbook, the Store Allocation Type will display "unavailable" for any invalid combinations (no store source, not on supply, or invalid store ordering packsize). If the watershed calculation changes the allocation quantity, the Store User Specified Allocation is changed to "Replace". (Read only)
Store Ordering Pack Size	The Store Ordering Pack Size represents the primary pack size to be used when ordering a SKU for a store (either from a warehouse or from a supplier). Note: Store Ordering Pack Size is loaded from Data Management online (DMo). The allocation must be a multiple of the store ordering pack size (Read only)

Measure Label	Description
Store Percent of Pallet (expanded)	Percent of pallet is used to determine if the Ideal Receipt Quantity for replenishment should be rounded to a full pallet. It represents the percentage threshold that case demand must exceed in order for pallet rounding to occur. The expanded version of Store Percent of Pallet will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered. (Read only)
Store Source Label	The Store Source Label identifies the source from which this store receives inventory. (Read only)
Store User Specified Allocation	The Store User Specified Allocation represents the number of units to replace or add to an unreleased store order. When the source stocking point units are allocated to the stores using the watershed, algorithm, the Store User Specified Allocation changes to reflect the number of units each store was allocated. Since the allocations must be rounded to packsize, the total allocation quantity from the source may not be met. The Store User Specified Allocation is only updated in the database if the Allocation type is "Replace". (Read only)
USA AOI Allocation Index	The USA AOI Allocation Index is calculated as the sum of the days selected to build the index. The watershed algorithm uses the index to determine the ratio for distributing the units across the stores. (Read only)
USA Maximum Shipping Units per store	The USA Maximum Shipping Units per store represents the maximum quantity that can be shipped to the store for this product. The Specified Allocation cannot exceed this value. Any positive integer, including zero, is valid. The USA Maximum Shipping Units per store is only updated in the database if the Allocation type is "Replace".
USA Minimum Shipping Units per store	The USA Minimum Shipping Units per store represents the minimum quantity that can be shipped to the store for this product. The Specified Allocation must be equal to or greater than this value. Any positive integer, including zero, is valid. The USA Minimum Shipping Units per store is only updated in the database if the Allocation type is "Replace".
USA Number of packs per store	When the "Store User Specified Allocation" value changes, the number of packs is calculated as the Store User Specified Allocation divided by the USA Number of packs per store. (Read only)

USA Create Rule Based Index Workbook

The USA Create Rule Based Index workbook allows you to create a rule based index used in the Allocation On Index workbooks. The rule based index can be based on one of 3 key measures: Store Adjusted Sales, Store Receipt Plan, and Store Demand Forecast.

This workbook contains one worksheet that is grouped into a single tab:

- USA Create Rule Based Index tab
 - USA Create Rule Based Index Worksheet

USA Create Rule Based Index Workbook Wizard

Available Days

The dialog box for Available Days shows a list of all dates with the user's previous selections already selected. The user has the ability to re-select dates to be accessed in the workbook. If multiple days are selected, they must be consecutive days. Standard RPAS functionality is available for this page.

To use the Store Adjusted Sales as the basis for the rule based index the user must select days in the past. For Store Receipt Plan or Store Demand Forecast, days in the future must be selected.


The screenshot shows the 'USA Create Rule Based Index Wizard' dialog box with the 'Available Days' tab selected. The 'Available Days' list on the left contains dates from 03/27/05 to 04/14/05. Dates from 04/01/05 to 04/05/05 are checked. The 'Selected Days' list on the right shows the same dates (04/01/05 to 04/05/05). The 'Position Query Definitions' tab is also visible. At the bottom, there are buttons for 'Cancel', '<Back', 'Next>', 'Finish', and 'Help'. A checkbox for 'Synchronize hierarchies' is also present.

Available Days	Selected Days
☐ 03/27/05	• 04/01/05
☐ 03/28/05	• 04/02/05
☐ 03/29/05	• 04/03/05
☐ 03/30/05	• 04/04/05
☐ 03/31/05	• 04/05/05
☒ 04/01/05	
☒ 04/02/05	
☒ 04/03/05	
☒ 04/04/05	
☒ 04/05/05	
☐ 04/06/05	
☐ 04/07/05	
☐ 04/08/05	
☐ 04/09/05	
☐ 04/10/05	
☐ 04/11/05	
☐ 04/12/05	
☐ 04/13/05	
☐ 04/14/05	

USA Create Rule Based Index Wizard – Available Days

Available SKUs


The dialog box for Available SKUs displays a list of all SKUs with the user's previous selections already selected. The user has the ability to re-select which SKUs will be accessed in the workbook. Standard RPAS functionality is available for this wizard page.



USA Create Rule Based Index Wizard – Available SKUs

Available Stores

The dialog box for Available Stores shows a list of all Stores with the user's previous selections already selected. The user has the ability to re-select which Stores will be accessed in the workbook. Standard RPAS functionality is available for this wizard page.



USA Create Rule Based Index Wizard – Available Stores

Select Finish. The workbook is built using the SKUs, Stores, and Days selected.

USA Create Rule Based Index Tab

USA Create Rule Based Index Worksheet

The USA Create Rule Based Index Worksheet allows the user to create the rule based index based on adjusted sales, demand forecast, or store receipt plan.

Measure	Value
Store Adjusted Sales	0.00
Store Demand Forecast	0.00
Store Receipt Plan	0.00
USA Index Notes	
USA Rule Based Manual Index	200.00

USA Create Rule Based Index Worksheet

The following measures are displayed automatically when using the default template.

Measure Label	Description
Store Adjusted Sales	Store Adjusted Sales represents historical adjusted store sales information used to establish the adjusted sales history for the USA Allocation On Rule Based Index USA workbook. It is calculated as the sum of adjusted sales for the days selected in the wizard. To use this measure as the rule based manual index, the user manually copies the value into the USA Rule Based Manual Index. (Read only)
Store Demand Forecast	Store Demand Forecast is calculated as the sum of the demand forecast for the days selected in the wizard. To use this measure as the rule based manual index, the user manually copies the value into the USA Rule Based Manual Index. (Read only)
Store Receipt Plan	Store Receipt Plan is calculated as the sum of the store receipts for the days selected in the wizard. To use this measure as the rule based manual index, the user manually copies the value into the USA Rule Based Manual Index. (Read only)
USA Index Notes	USA Index Notes allows entry of a note for the rule based manual index.

Measure Label	Description
USA Rule Based Manual Index	The USA Rule Based Manual Index is used in the USA Allocation on Rule Based Index workbook as input to the watershed algorithm to determine the ratio for distributing the units across the stores for Store User Specified Allocation. It is manually entered by the user or manually copied from one of the three rules in this worksheet: ▪ Store Adjusted Sales ▪ Store Demand Forecast ▪ Store Receipt Plan

USA Allocation on Rule Based Index Workbook

The USA Allocation on Rule Based Index workbook allows the user to specify a quantity at the source stocking point to spread proportionally across a set of stores taking into account the store inventory. The ratio for this spread is based on the USA Rule Based Manual Index for the SKU/Store combination. The USA Rule Based Manual Index must first be set up in the USA Create Rule Based Index Workbook. A Watershed Algorithm is used in the allocation of these quantities to the store level.

This workbook contains three worksheets that are grouped into a single tab:

- USA Allocation on Rule Based Index tab
 - Store Level Information Worksheet
 - Warehouse Level Information Worksheet
 - Supplier Level Information Worksheet

USA Allocation on Rule Based Index Workbook Wizard


Available Receive On Days

Available Receive On Days displays a list of all dates from tomorrow through the maximum planning horizon. Only one Selected Receive On Day is allowed. The user's previous selection is not already selected. The user has the ability to select which date will be accessed in the workbook. Standard RPAS functionality is available for this wizard page.

The screenshot shows the 'USA Allocation on Rule Based Index Wizard' dialog box. It has a title bar with a close button. The main area is divided into two panes. The left pane, titled 'Available Receive on Days', contains a list of dates from 04/02/06 to 04/15/06. The date 04/03/06 is selected with a red checkmark. The right pane, titled 'Selected Receive on Day', contains the date 04/03/06. Below the panes is a checkbox labeled 'Synchronize hierarchies'. At the bottom are five buttons: 'Cancel', '<Back', 'Next>', 'Finish', and 'Help'.

USA Allocation on Rule Based Index Wizard – Available Receive on Days

If multiple days are selected the user will be warned that only one date may be chosen.




Available SKUs

The dialog box for Available SKUs wizard screen displays a list of all SKUs that


- Have a Source for the store on the day selected
- Are On Supply for any store on either the day selected or any date within the planning horizon
- Have a valid Store Ordering Pack Size on the day selected

The user's previous selections are not already selected. The user has the ability to select which SKUs will be accessed in the workbook. Standard RPAS functionality is available for this wizard page.




USA Allocation on Rule Based Index Wizard – Available SKUs

If no filtering criteria were met for any SKU based on the receive-on date selected from the previous wizard screen, the user is notified by the following warning message appears.



Available Source Stocking Points

The Available Source Stocking Points wizard screen displays a list of all Source Stocking Points for the SKUs and day selected. The user's previous selections are not already selected. The user has the ability to select which Source Stocking Points will be accessed in the workbook. Standard RPAS functionality is available for this wizard page.




USA Allocation on Rule Based Index Wizard – Available Source Stocking Points

Note: If no warehouse stocking point is selected, the first warehouse found is brought into the workbook. If no supplier stocking point is selected, the first supplier found is brought into the workbook.

Available Stores

The dialog box for Available Stores wizard screen displays a list of all Stores sourced by the selected Source Stocking Point for the SKUs and day selected and the SKU is On Supply within the planning horizon.

The user's previous selections are not already selected. The user has the ability to select which Stores will be accessed in the workbook. Standard RPAS functionality is available for this wizard page.



USA Allocation on Rule Based Index Wizard – Available Stores

The USA Allocation on Rule Based Index Workbook will contain 1 tab: USA Allocation on Rule Based Index.

USA Allocation on Rule Based Index Tab

Store Level Information Worksheet

The Store Level Information worksheet displays the calculated USA quantity, AOI Index quantity, store specific pack size, cases per pallet, and source level information. It also provides the ability to enter maximum and minimum boundaries by store for the AOI quantity that is being pushed from the warehouse.

Product	Location	Calendar
100035008 - CALCULATOR, GRAPHING, S	S303 - MISH	04/03/06
Cases Per Pallet	0	
Store Allocation Type	Add	
Store Ordering Pack Size	1.00	
Store Percent of Pallet (expanded)	0.00	
Store Source Label	W1090 - MIP	
Store User Specified Allocation	100.00	
USA AOI Allocation Index	0	
USA Maximum Shipping Units per store	999999.00	
USA Minimum Shipping Units per store	0.00	
USA Number of packs per store	100	

Measure < [] >

Store Level Information Worksheet

The following measures are displayed automatically when using the default template.

Measure Label	Description
Cases Per Pallet	Cases Per Pallet reflects the number of cases on a pallet. Note: Cases Per Pallet is loaded from Data Management online (DMo). (Read only)
Store Allocation Type	The Store Allocation Type is always "Replace" for AOI. Upon opening the workbook, the Store Allocation Type will display "unavailable" for any invalid combinations (no store source, not on supply, or invalid store ordering packsize). If the watershed calculation changes the allocation quantity, the Store User Specified Allocation is changed to "Replace". (Read only)
Store Ordering Pack Size	The Store Ordering Pack Size represents the primary pack size to be used when ordering a SKU for a store (either from a warehouse or from a supplier). Note: Store Ordering Pack Size is loaded from Data Management online (DMo). The allocation must be a multiple of the store ordering pack size (Read only)

Measure Label	Description
Store Percent of Pallet (expanded)	Percent of pallet is used to determine if the Ideal Receipt Quantity for replenishment should be rounded to a full pallet. It represents the percentage threshold that case demand must exceed in order for pallet rounding to occur. The expanded version of Store Percent of Pallet will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered. (Read only)
Store Source Label	The Store Source Label identifies the source from which this store receives inventory. (Read only)
Store User Specified Allocation	The Store User Specified Allocation represents the number of units to replace an unreleased store order. When the source stocking point units are allocated to the stores using the watershed, algorithm, the Store User Specified Allocation changes to reflect the number of units each store was allocated. Since the allocations must be rounded to packsize, the total allocation quantity from the source may not be met. The Store User Specified Allocation is only updated in the database if the Allocation type is "Replace". (Read only)
USA AOI Allocation Index	The USA AOI Allocation Index represents the value in the USA Rule Based Manual Index and is used in the watershed algorithm to determine the ratio for distributing the units across the stores for Store User Specified Allocation. Note: The USA Rule Based Manual Index must first be set up in the USA Create Rule Based Index Workbook. (Read only)
USA Maximum Shipping Units per store	The USA Maximum Shipping Units per store represents the maximum quantity that can be shipped to the store for this product. Store User The Specified Allocation cannot exceed this value. Any positive integer, including zero, is valid. The USA Maximum Shipping Units per store is only updated in the database if the Allocation type is "Replace".
USA Minimum Shipping Units per store	The USA Minimum Shipping Units per store represents the minimum quantity that can be shipped to the store for this product. Store User The Specified Allocation must be equal to or greater than this value. Any positive integer, including zero, is valid. The USA Minimum Shipping Units per store is only updated in the database if the Allocation type is "Replace".
USA Number of packs per store	When the "Store User Specified Allocation" value changes, the number of packs is calculated as the Store User Specified Allocation divided by the USA Number of packs per store. (Read only)

Warehouse Level Information Worksheet

The Warehouse Level Information worksheet provides the ability to push USAs based on an allocation index to stores. This worksheet displays the earliest release date and warehouse inventory information. It also provides the ability to enter warehouse allocation maximum and minimum boundaries and a total allocation quantity to be pushed to stores. This can either be in units or cases.

Measure	Value
USA AOI WH Allocate by Store	☐
USA AOI WH Allocation Status by Store	☐
USA Earliest WH Release Date by Store	4/2/2006
USA Total Allocated WH Cases by Store	100
USA Total Allocated WH Units by Store	100.00
USA WH Maximum Shipping Units	999999.00
USA WH Minimum Shipping Units	0.00
USA WH Percent of Pallet	0
USA WH Projected Inventory	0.00

Warehouse Level Information Worksheet

The following measures are displayed automatically when using the default template.

Measure Label	Description
USA AOI WH Allocate by Store	USA AOI WH Allocate by Store is a checkbox used to start the watershed algorithm to push the USA Total Allocated WH Units by Store across all stores in the workbook that are sourced by this warehouse.
USA AOI WH Allocation Status by Store	The USA AOI WH Allocation Status by Store indicates the warehouse level status of the algorithm. - Solution Found indicates the allocation was successful - Invalid Distribute Quantity indicates the allocation quantity was less than the sum of all the store minimums or greater than the sum of all the maximums - Invalid Shipping Quantity indicates the maximum and minimum shipping quantities are invalid (Read only)
USA Earliest WH Release Date by Store	The USA Earliest WH Release Date by Store is calculated based on the maximum lead time for the stores sourced by this warehouse. For Delivery Window USAs, the earliest release date is the greater of the lead time and delivery window for the stores sourced by this warehouse. If the Release Date is aggregated to a higher level, the value of the earliest release date is displayed. (Read only)

Measure Label	Description
USA Total Allocated WH Cases by Store	The USA Total Allocated WH Cases by Store is the total of the USA Number of packs per store of this SKU for all stores in the workbook sourced by this warehouse. (Read only)
USA Total Allocated WH Units by Store	The USA Total Allocated WH Units by Store is the total of the Store User Specified Allocation of this SKU for all stores in the workbook sourced by this warehouse. The user can override this calculated quantity to change the allocation quantity to be pushed down to the stores sourced by this warehouse. The push will not happen until the USA AOI WH Allocate by Store option is checked.
USA WH Maximum Shipping Units	USA WH Maximum Shipping Units represents the average of the USA Maximum Shipping Units per for all stores in the workbook sourced by this warehouse. The user can override this calculated quantity to change the maximum to be pushed down to the stores sourced by this warehouse.
USA WH Minimum Shipping Units	The USA WH Minimum Shipping Units per store represents the minimum quantity that can be shipped to the store for this product. The user can override this calculated quantity to change the minimum to be pushed down to the stores sourced by this warehouse.
USA WH Percent of Pallet	The USA WH Percent of Pallet is percent of pallet of this SKU for all stores in the workbook sourced by this warehouse. If the values are different, a question mark (?) will be displayed. (Read only)
USA WH Projected Inventory	USA WH Projected Inventory represents the total projected inventory of this SKU shifted by lead time at the source warehouse. The day the projected inventory is shown for each SKU corresponds to the earliest warehouse release day when there are multiple release days for a single receipt date at any of the stores (in other words, corresponding to the max lead time). (Read only)

Supplier Level Information Worksheet

The Supplier Level Information worksheet provides the ability to push USAs based on an allocation index to stores. This worksheet displays the earliest release date and provides the ability to enter supplier allocation maximum and minimum boundaries and a total allocation quantity to be pushed to stores. This can either be in units or cases.

Supplier Level Information Worksheet

The following measures are displayed automatically when using the default template.

Measure Label	Description
USA AOI Supplier Allocate by Store	USA AOI Supplier Allocate by Store is a checkbox used to start the watershed algorithm to push the USA Total Allocated Supplier Units by Store across all stores in the workbook that are sourced by this supplier.
USA AOI Supplier Allocation Status by Store	The USA AOI Supplier Allocation Status by Store indicates the supplier level status of the algorithm. - Solution Found indicates the allocation was successful - Invalid Distribute Quantity indicates the allocation quantity was less than the sum of all the store minimums or greater than the sum of all the maximums - Invalid Shipping Quantity indicates the maximum and minimum shipping quantities are invalid (Read only)
USA Earliest Supplier Release Date by Store	The USA Earliest Supplier Release Date by Store is calculated based on the maximum lead time for the stores sourced by this supplier. If the Release Date is aggregated to a higher level, the value of the earliest release date is displayed. (Read only)
USA Supplier Maximum Shipping Units	USA Supplier Maximum Shipping Units represents the average of the USA Maximum Shipping Units per for all stores in the workbook sourced by this supplier. The user can override this calculated quantity to change the maximum to be pushed down to the stores sourced by this supplier.

Measure Label	Description
USA Supplier Minimum Shipping Units	The USA Supplier Minimum Shipping Units per store represents the minimum quantity that can be shipped to the store for this product. The user can override this calculated quantity to change the minimum to be pushed down to the stores sourced by this supplier.
USA Total Allocated Supplier Cases by Store	The USA Total Allocated Supplier Cases by Store is the total of the USA Number of packs per store of this SKU for all stores in the workbook sourced by this supplier. (Read only)
USA Total Allocated Supplier Units by Store	The USA Total Allocated Supplier Units by Store is the total of the Store User Specified Allocation of this SKU for all stores in the workbook sourced by this supplier. The user can override this calculated quantity to change the allocation quantity to be pushed down to the stores sourced by this warehouse. The push will not happen until the USA AOI WH Allocate by Store option is checked.

USA Create Store Based Index Workbook

The USA Create Store Based Index workbook allows the user to create a store based index that is used in the USA Allocation on Store Based Index workbook. The user can reference key measures (Store Adjusted Sales, Store Receipt Plan, and Store Demand Forecast) to create a store based index. The label and description for the USA Store Based Manual Index can be changed to help identify the Index.

This workbook contains three worksheets that are grouped into a single tab:

- USA Create Store Based Index tab
 - Reference Measures Worksheet
 - Label and Description Change Information Worksheet
 - Store Based Manual Index Worksheet

USA Create Store Based Index Wizard

Available Days

The dialog box for Available Days shows a list of all dates with the user's previous selections already selected. The user has the ability to re-select dates to be accessed in the workbook. If multiple days are selected, they must be consecutive days. Standard RPAS functionality is available for this page.

To use the Store Adjusted Sales as the basis for the rule based index the user must select days in the past. For Store Receipt Plan or Store Demand Forecast, days in the future must be selected.

The screenshot shows the 'USA Create Store Based Index Wizard' dialog box. It has a title bar with the text 'USA Create Store Based Index Wizard' and a close button. The main area is divided into two panes: 'Available Days' on the left and 'Selected Days' on the right. The 'Available Days' pane contains a list of dates from 03/26/05 to 04/13/05. The dates 04/01/05, 04/02/05, 04/03/05, 04/04/05, and 04/05/05 are checked. The 'Selected Days' pane contains a list of the same dates: 04/01/05, 04/02/05, 04/03/05, 04/04/05, and 04/05/05. Below the panes is a checkbox labeled 'Synchronize hierarchies'. At the bottom are five buttons: 'Cancel', '<Back', 'Next>', 'Finish', and 'Help'.

Available Days	Selected Days
☐ 03/26/05	• 04/01/05
☐ 03/27/05	• 04/02/05
☐ 03/28/05	• 04/03/05
☐ 03/29/05	• 04/04/05
☐ 03/30/05	• 04/05/05
☐ 03/31/05	
☒ 04/01/05	
☒ 04/02/05	
☒ 04/03/05	
☒ 04/04/05	
☒ 04/05/05	
☐ 04/06/05	
☐ 04/07/05	
☐ 04/08/05	
☐ 04/09/05	
☐ 04/10/05	
☐ 04/11/05	
☐ 04/12/05	
☐ 04/13/05	


☐ Synchronize hierarchies

Buttons: Cancel, <Back, Next>, Finish, Help

USA Create Store Based Index Wizard – Available Days

Available SKUs


The dialog box for Available SKUs displays a list of all SKUs with the user's previous selections already selected. The user has the ability to re-select which SKUs will be accessed in the workbook. Standard RPAS functionality is available for this wizard page.



USA Create Store Based Index Wizard – Available SKUs

Available Stores


The dialog box for Available Stores shows a list of all Stores with the user's previous selections already selected. The user has the ability to re-select which Stores will be accessed in the workbook. Standard RPAS functionality is available for this wizard page.



USA Create Store based Index Wizard – Available Stores


Available USAs

The dialog box for Available USAs displays a list of all USAs with the user's previous selections already selected. The user has the ability to re-select which USAs will be accessed in the workbook. Standard RPAS functionality is available for this wizard page.



USA Create Store Based Index Wizard – Available USAs

The user can display position attributes to see the associated label and description for each USA that was set up using the USA Create Store Based Index workbook. In order to see this, right click on the USA, select “Select display and sort attributes...” and click the USA Manual Index Label and USA Manual Index Description to the right for Display Attributes.



USA Create Store Based Index Wizard – Selectable USAs

Select Finish. The workbook is built using the SKUs, Stores, and USAs selected.

USA Create Store Based Index Tab

Reference Measures Worksheet

The Reference Measures Worksheet allows the user to view adjusted sales, demand forecast, or store receipt plan measures that can be used to create the store based index.

Reference Measures

Product	Location	Calendar			
100035008 - CALCULATOR,GRAPHING,: S1000000001 - Minne					
	04/01/05	04/02/05	04/03/05	04/04/05	04/05/05
Store Adjusted Sales	0.00	0.00	0.00	0.00	0.00
Store Demand Forecast	0.00	0.00	0.00	0.00	0.00
Store Receipt Plan	0.00	0.00	0.00	0.00	0.00
Measure					


Reference Measures Worksheet

The following measures appear automatically when using the default template.

Measure Label	Description
Store Adjusted Sales	Store Adjusted Sales represents historical adjusted store sales information used to establish the adjusted sales history for the USA Allocation On Store Based Index USA workbook. It is calculated as the sum of adjusted sales for the days selected in the wizard. (Read only)
Store Demand Forecast	Store Demand Forecast is calculated as the sum of the demand forecast for the days selected in the wizard. (Read only)
Store Receipt Plan	Store Receipt Plan is calculated as the sum of the store receipts for the days selected in the wizard. (Read only)

Label and Description Change Information Worksheet

The Label and Description Change Information Worksheet allows the user to create or update USA Manual Index Descriptions and Labels.



Label and Description Change Information

The following measures appear automatically when using the default template.

Measure Label	Description
USA Manual Index Description	The USA Manual Index Description contains a user-entered description of a Store Based Index. In order to see the description in wizards and other worksheets, right click on the USA, select "Select display and sort attributes..." and click USA Manual Index Description to the right for Display Attributes. To allow the description to be referenced for future workbook builds, the USA Manual Index Flag must be checked.
USA Manual Index Flag	The USA Manual Index Flag enables users to create custom labels and descriptions for USA manual indexes. This flag must be checked in order for label and description to be created in the next AIP batch run.

Measure Label	Description
USA Manual Index Label	The USA Manual Index Label is a user-entered label created by users to identify a USA manual index. In order to see the index label in wizards and other worksheets, right click on the USA, select “Select display and sort attributes...” and click USA Manual Index Label to the right for Display Attributes. To allow the index label to be referenced for future workbook builds, the USA Manual Index Flag must be checked.

Store Based Manual Index Worksheet

The Store Based Manual Index Worksheet allows the user to create the store based index based on adjusted sales, demand forecast, or store receipt.

Store Based Manual Index Worksheet

The following measures are displayed automatically when using the default template.

Measure Label	Description
USA Store Based Manual Index	The USA Store Based Manual Index is used in the USA Allocation on Index (AOI) workbooks. It is manually entered by the user or manually copied from one of the three rules in the Reference Measures worksheet: ▪ Store Adjusted Sales ▪ Store Demand Forecast ▪ Store Receipt Plan

USA Allocation on Store Based Index Workbook

The USA Allocation on Store Based Index workbook allows the user to specify a quantity at the source stocking point to spread proportionally across a set of stores taking into account the store inventory. The ratio for this spread is based on the USA Store Based Manual Index for the SKU/Store combination. The USA Store Based Manual Index must first be set up in the USA Create Store Based Index Workbook. A Watershed Algorithm is used in the allocation of these quantities to the store level.

This workbook contains three worksheets that are grouped into a single tab:

- USA Allocation on Store Based Index tab
 - Store Level Information Worksheet
 - Warehouse Level Information Worksheet
 - Supplier Level Information Worksheet

USA Allocation on Store Based Index Wizard


Available Receive On Days

Available Receive On Days displays a list of all dates from tomorrow through the maximum planning horizon. Only one Selected Receive On Day is allowed. The user's previous selection is not already selected. The user has the ability to select which date will be accessed in the workbook. Standard RPAS functionality is available for this wizard page.

The screenshot shows a Windows-style dialog box titled "USA Allocation on Store Based Index Wizard". It has a blue title bar with a close button (X) in the top right corner. The main area is divided into two panes. The left pane, titled "Available Receive on Days", contains a list of dates from 04/02/06 to 04/15/06, each with a checkbox. The date 04/03/06 is selected, indicated by a red checkmark and a dashed border around the text. The right pane, titled "Selected Receive on Day", contains a single entry: 04/03/06, preceded by a bullet point. Below the panes is a checkbox labeled "Synchronize hierarchies" which is currently unchecked. At the bottom of the dialog are five buttons: "Cancel", "<Back", "Next>", "Finish", and "Help".

USA Allocation on Store Based Index Wizard – Available Receive on Days

If multiple days are selected the user will be warned that only one date may be chosen.




Available SKUs

The dialog box for Available SKUs wizard screen displays a list of all SKUs that


- Have a Source for the store on the day selected
- Are On Supply for any store on either the day selected or any date within the planning horizon
- Have a valid Store Ordering Pack Size on the day selected

The user's previous selections are not already selected. The user has the ability to select which SKUs will be accessed in the workbook. Standard RPAS functionality is available for this wizard page.




USA Allocation on Store Based Index Wizard – Available SKUs

If no filtering criteria were met for any SKU based on the receive-on date selected from the previous wizard screen, the user will be notified by the following warning message.



Available Source Stocking Points

The Available Source Stocking Points wizard screen displays a list of all Source Stocking Points for the SKUs and day selected. The user's previous selections are not already selected. The user has the ability to select which Source Stocking Points will be accessed in the workbook. Standard RPAS functionality is available for this wizard page.




USA Allocation on Store Based Index Wizard – Available Source Stocking Points

Note: If no warehouse stocking point is selected, the first warehouse found is brought into the workbook. If no supplier stocking point is selected, the first supplier the first supplier found is brought into the workbook.

Available Stores

The dialog box for Available Stores wizard screen displays a list of all Stores sourced by the selected Source Stocking Point for the SKUs and day selected and the SKU is On Supply.


The user's previous selections are not already selected. The user has the ability to select which Stores will be accessed in the workbook. Standard RPAS functionality is available for this wizard page.



USA Allocation on Store Based Index Wizard – Available Stores


Available USAs

The dialog box for Available USAs shows a list of all USAs. The user's previous selection is already selected. The user has the ability to re-select which USA will be accessed in the workbook. Only one selection can be made. Standard RPAS functionality is available for this wizard page.



USA Allocation on Store Based Index Wizard – Available USAs

If the user selects more than one USA, the warning “Only one USA position can be selected.” is issued.



When the user selects 'Finish', the workbook will be built using the SKUs, Stores and Day selected.

USA Allocation on Store Based Index Tab

Store Level Information Worksheet

The Store Level Information worksheet displays the calculated USA quantity, AOI Index quantity, store specific pack size, cases per pallet, and source level information. It also provides the ability to enter maximum and minimum boundaries by store for the AOI quantity that is being pushed from the warehouse

Store Level Information Worksheet

The following measures are displayed automatically when using the default template.

Measure Label	Description
Cases Per Pallet	Cases Per Pallet reflects the number of cases on a pallet. Note: Cases Per Pallet is loaded from Data Management online (DMo). (Read only)
Store Allocation Type	The Store Allocation Type indicates whether the allocation should be added to the receipt plan calculation or whether it should act as a replacement of the receipt plan. Upon opening the workbook, the Store Allocation Type will display "unavailable" for any invalid combinations (no store source, not on supply, or invalid store ordering packsize). If the watershed calculation changes the allocation quantity, the Store User Specified Allocation is changed to "Replace". (Read only)
Store Ordering Pack Size	The Store Ordering Pack Size represents the primary pack size to be used when ordering a SKU for a store (either from a warehouse or from a supplier). Note: Store Ordering Pack Size is loaded from Data Management online (DMo). The allocation must be a multiple of the store ordering pack size (Read only)

Measure Label	Description
Store Percent of Pallet (expanded)	Percent of pallet is used to determine if the Ideal Receipt Quantity for replenishment should be rounded to a full pallet. It represents the percentage threshold that case demand must exceed in order for pallet rounding to occur. The expanded version of Store Percent of Pallet will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered. (Read only)
Store Source Label	The Store Source Label identifies the source from which this store receives inventory. (Read only)
Store User Specified Allocation	The Store User Specified Allocation represents the number of units to replace an unreleased store order. When the source stocking point units are allocated to the stores using the watershed, algorithm, the Store User Specified Allocation changes to reflect the number of units each store was allocated. Since the allocations must be rounded to packsize, the total allocation quantity from the source may not be met. The Store User Specified Allocation is only updated in the database if the Allocation type is "Replace". (Read only)
USA AOI Allocation Index	The USA AOI Allocation Index represents the value in the USA Store Based Manual Index and is used in the watershed algorithm to determine the ratio for distributing the units across the stores for Store User Specified Allocation. Note: The USA Rule Based Manual Index must first be set up in the USA Create Store Based Index Workbook. (Read only)
USA Maximum Shipping Units per store	The USA Maximum Shipping Units per store represents the maximum quantity that can be shipped to the store for this product. Store User The Specified Allocation cannot exceed this value. Any positive integer, including zero, is valid. The USA Maximum Shipping Units per store is only updated in the database if the Allocation type is "Replace".
USA Minimum Shipping Units per store	The USA Minimum Shipping Units per store represents the minimum quantity that can be shipped to the store for this product. Store User The Specified Allocation must be equal to or greater than this value. Any positive integer, including zero, is valid. The USA Minimum Shipping Units per store is only updated in the database if the Allocation type is "Replace".
USA Number of packs per store	When the "Store User Specified Allocation" value changes, the number of packs is calculated as the Store User Specified Allocation divided by the USA Number of packs per store. (Read only)

Warehouse Level Information Worksheet

The Warehouse Level Information worksheet provides the ability to push USAs based on an allocation index to stores. This worksheet displays the earliest release date and warehouse inventory information. It also provides the ability to enter warehouse allocation maximum and minimum boundaries and a total allocation quantity to be pushed to stores. This can either be in units or cases.

Product	Warehouse	Calendar
100035008 - CALCULATOR, GRAPHING, SI	W1090 - MI	
	04/03/06	
USA AOI WH Allocate by Store		
USA AOI WH Allocation Status by Store		
USA Earliest WH Release Date by Store	4/2/2006	
USA Total Allocated WH Cases by Store	100	
USA Total Allocated WH Units by Store	100.00	
USA WH Maximum Shipping Units	999999.00	
USA WH Minimum Shipping Units	0.00	
USA WH Percent of Pallet	0	
USA WH Projected Inventory	0.00	

Warehouse Level Information Worksheet

The following measures appear automatically when using the default template.

Measure Label	Description
Cases Per Pallet	Cases Per Pallet reflects the number of cases on a pallet. Note: Cases Per Pallet is loaded from Data Management online (DMo). (Read only)
Store Allocation Type	The Store Allocation Type indicates whether the allocation should be added to the receipt plan calculation or whether it should act as a replacement of the receipt plan. Upon opening the workbook, the Store Allocation Type will display "unavailable" for any invalid combinations (no store source, not on supply, or invalid store ordering packsize). If the watershed calculation changes the allocation quantity, the Store User Specified Allocation is changed to "Replace". (Read only)
Store Ordering Pack Size	The Store Ordering Pack Size represents the primary pack size to be used when ordering a SKU for a store (either from a warehouse or from a supplier). Note: Store Ordering Pack Size is loaded from Data Management online (DMo). The allocation must be a multiple of the store ordering pack size (Read only)

Measure Label	Description
Store Percent of Pallet (expanded)	Percent of pallet is used to determine if the Ideal Receipt Quantity for replenishment should be rounded to a full pallet. It represents the percentage threshold that case demand must exceed in order for pallet rounding to occur. The expanded version of Store Percent of Pallet will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered. (Read only)
Store Source Label	The Store Source Label identifies the source from which this store receives inventory. (Read only)
Store User Specified Allocation	The Store User Specified Allocation represents the number of units to replace an unreleased store order. When the source stocking point units are allocated to the stores using the watershed, algorithm, the Store User Specified Allocation changes to reflect the number of units each store was allocated. Since the allocations must be rounded to packsize, the total allocation quantity from the source may not be met. The Store User Specified Allocation is only updated in the database if the Allocation type is "Replace". (Read only)
USA AOI Allocation Index	The USA AOI Allocation Index represents the value in the USA Store Based Manual Index and is used in the watershed algorithm to determine the ratio for distributing the units across the stores for Store User Specified Allocation. Note: The USA Rule Based Manual Index must first be set up in the USA Create Store Based Index Workbook. (Read only)
USA Maximum Shipping Units per store	The USA Maximum Shipping Units per store represents the maximum quantity that can be shipped to the store for this product. Store User The Specified Allocation cannot exceed this value. Any positive integer, including zero, is valid. The USA Maximum Shipping Units per store is only updated in the database if the Allocation type is "Replace".
USA Minimum Shipping Units per store	The USA Minimum Shipping Units per store represents the minimum quantity that can be shipped to the store for this product. Store User The Specified Allocation must be equal to or greater than this value. Any positive integer, including zero, is valid. The USA Minimum Shipping Units per store is only updated in the database if the Allocation type is "Replace".
USA Number of packs per store	When the "Store User Specified Allocation" value changes, the number of packs is calculated as the Store User Specified Allocation divided by the USA Number of packs per store. (Read only)

Supplier Level Information Worksheet

The Supplier Level Information worksheet provides the ability to push USAs based on an allocation index to stores. This worksheet displays the earliest release date and provides the ability to enter supplier allocation maximum and minimum boundaries and a total allocation quantity to be pushed to stores. This can either be in units or cases.

Supplier Level Information Worksheet

The following measures are displayed automatically when using the default template.

Measure Label	Description
Cases Per Pallet	Cases Per Pallet reflects the number of cases on a pallet. Note: Cases Per Pallet is loaded from Data Management online (DMo). (Read only)
Store Allocation Type	The Store Allocation Type indicates whether the allocation should be added to the receipt plan calculation or whether it should act as a replacement of the receipt plan. Upon opening the workbook, the Store Allocation Type will display “unavailable” for any invalid combinations (no store source, not on supply, or invalid store ordering packsize). If the watershed calculation changes the allocation quantity, the Store User Specified Allocation is changed to “Replace”. (Read only)
Store Ordering Pack Size	The Store Ordering Pack Size represents the primary pack size to be used when ordering a SKU for a store (either from a warehouse or from a supplier). Note: Store Ordering Pack Size is loaded from Data Management online (DMo). The allocation must be a multiple of the store ordering pack size (Read only)

Measure Label	Description
Store Percent of Pallet (expanded)	Percent of pallet is used to determine if the Ideal Receipt Quantity for replenishment should be rounded to a full pallet. It represents the percentage threshold that case demand must exceed in order for pallet rounding to occur. The expanded version of Store Percent of Pallet will display the actual value used in the calculations. This is the merge of exception level (SKU/Store/Day), default level (Sub-class/Store format), and global level (Dept) values entered. (Read only)
Store Source Label	The Store Source Label identifies the source from which this store receives inventory. (Read only)
Store User Specified Allocation	The Store User Specified Allocation represents the number of units to replace an unreleased store order. When the source stocking point units are allocated to the stores using the watershed, algorithm, the Store User Specified Allocation changes to reflect the number of units each store was allocated. Since the allocations must be rounded to packsize, the total allocation quantity from the source may not be met. The Store User Specified Allocation is only updated in the database if the Allocation type is "Replace". (Read only)
USA AOI Allocation Index	The USA AOI Allocation Index represents the value in the USA Store Based Manual Index and is used in the watershed algorithm to determine the ratio for distributing the units across the stores for Store User Specified Allocation. Note: The USA Rule Based Manual Index must first be set up in the USA Create Store Based Index Workbook. (Read only)
USA Maximum Shipping Units per store	The USA Maximum Shipping Units per store represents the maximum quantity that can be shipped to the store for this product. Store User The Specified Allocation cannot exceed this value. Any positive integer, including zero, is valid. The USA Maximum Shipping Units per store is only updated in the database if the Allocation type is "Replace".
USA Minimum Shipping Units per store	The USA Minimum Shipping Units per store represents the minimum quantity that can be shipped to the store for this product. Store User The Specified Allocation must be equal to or greater than this value. Any positive integer, including zero, is valid. The USA Minimum Shipping Units per store is only updated in the database if the Allocation type is "Replace".
USA Number of packs per store	When the "Store User Specified Allocation" value changes, the number of packs is calculated as the Store User Specified Allocation divided by the USA Number of packs per store. (Read only)

Delete USA Workbook

The Delete USA workbook allows the user to delete previously established USAs that have not been released. The user can delete a USA directly at the store level or can delete USAs across a warehouse and/or supplier.

If the USA Type is set to “Delete” instead of “Additive” or “Replacement,” the USA quantities are ignored during the store’s calculation process, and the USA quantity is not incorporated into the store replenishment plan. USAs can be deleted at the store, warehouse, or supplier level.

This workbook contains three worksheets that are grouped into a single tab:

- Delete USA tab
 - Delete USA Worksheet
 - Delete Warehouse USA Worksheet
 - Delete Supplier USA Worksheet

Delete USA Wizard

Available Days

The dialog box for Available Days shows a list of all dates from tomorrow through the end of the maximum planning horizon. The user’s previous selections are not already selected. The user has the ability to select which dates will be accessed in the workbook. If multiple days are selected, they do not have to be consecutive days. Standard RPAS functionality is available for this wizard page.


The screenshot shows the 'USA Delete Wizard' dialog box with the 'Available Days' tab selected. The 'Available Days' list on the left contains dates from 04/02/06 to 04/15/06. The date 04/03/06 is selected with a red checkmark. The 'Selected Days' list on the right shows 04/03/06. The 'Position Query Definitions' tab is also visible. At the bottom, there is a 'Synchronize hierarchies' checkbox and navigation buttons: Cancel, <Back, Next>, Finish, and Help.

Available Days	Selected Days
☐ 04/02/06	
☒ 04/03/06	● 04/03/06
☐ 04/04/06	
☐ 04/05/06	
☐ 04/06/06	
☐ 04/07/06	
☐ 04/08/06	
☐ 04/09/06	
☐ 04/10/06	
☐ 04/11/06	
☐ 04/12/06	
☐ 04/13/06	
☐ 04/14/06	
☐ 04/15/06	

Delete USA Wizard - Available Days


Available SKUs

The dialog box for Available SKUs shows a list of all SKUs that have a Store Allocation Type on the day(s) selected from the previous wizard screen. The user's previous selections are not already selected. The user has the ability to select which SKUs will be accessed in the workbook. Standard RPAS functionality is available for this wizard page.




Delete USA Wizard - Available SKUs

If there were no Store Allocation Types for the day(s) selected from the previous wizard screen, the user will be notified by the following warning message:



Available Stores

The dialog box for Available Stores displayed below will show a list of all Stores that have a Store Allocation Type on the day(s) and SKU(s) selected from the previous wizard screens. The user's previous selections are not already selected. The user has the ability to select which Stores will be accessed in the workbook. The positions default to the Store level. Standard RPAS functionality is available for this particular wizard page.



Delete USA Wizard - Available Stores

When the user selects 'Finish', the workbook will be built using the SKUs, Stores and Days selected.

Delete USA Tab

Delete USA Worksheet (SKU/store/day)

The Delete USA Worksheet allows deletion of USAs at the SKU/Store/Day level. After selecting a range of dates and SKUs in the wizard process, the user can view any existing USAs. The user can then identify USAs that should be deleted and check the USA Delete Allocation box to delete a USA.

Delete USA Worksheet

The following measures appear automatically when using the default template.

Measure Label	Description
Store Allocation Type	The Store Allocation Type indicates whether the allocation should be added to the receipt plan calculation or whether it should act as a replacement of the receipt plan. If USA Delete Allocation is checked, the allocation type is changed to 'Delete'. (Read only)
Store Source Label	The Store Source Label identifies the source from which this store receives inventory. (Read only)
Store User Specified Allocation	The Store User Specified Allocation represents the number of units to replace or add to an unreleased store order. The allocations displayed in this workbook are available for deletion. Checking the USA Delete Allocation option causes to store USA quantity to be cleared. (Read only)
USA Delete Allocation	The USA Delete Allocation is checked to delete the USA. If the delete allocation box is checked for a SKU/Store/Day combination, the Store User Specified Allocation quantity is cleared and the Store Allocation Type is changed to "Delete". On the appropriate Source (warehouse or supplier) worksheet, the amount of the USA deleted is reduced from the Source's USAs and the Source's Allocation Combination type will be updated.

Delete Warehouse USA Worksheet (SKU/Warehouse/Day)

The Delete Warehouse USA worksheet can be used to delete USAs at the SKU/Warehouse/Day level or to view the effect of deletions of Store USAs for stores sourced by this warehouse.

Deleting a Warehouse USA deletes all store USAs sourced by this warehouse/Day combination.

When a Store USA(s) is deleted, the Warehouses USA is updated to reflect the lower level changes.

Delete Warehouse USA Worksheet

The following measures are displayed automatically when using the default template.

Measure Label	Description
USA Delete Allocation at WH	The USA Delete Allocation is checked to delete all store USAs sourced by this warehouse/Day combination. The Store Allocation Type will be changed to "Delete" and the Store User Specified Allocation will be cleared for these stores.
USA Warehouse Allocation Type	The USA Warehouse Allocation Type is the allocation type of this SKU for all stores in the workbook sourced by this warehouse. If the values are different, a question mark (?) will be displayed. If the Allocation Type is not "unavailable", Valid values are: - None - Add - Replace - Delivery Window The Warehouse Allocation Type may be updated based on deletions of Store User Specified Allocations. (Read only)
USA Warehouse Summary	The USA Warehouse Summary displays the sum of all store USAs sourced by this warehouse/Day combination. If a store USA sourced by this warehouse is deleted, the warehouse User Specified Allocation Calculation is updated by subtracting the Store USA quantity from the Warehouse USA quantity. (Read only)

Delete Supplier USA Worksheet (SKU/supplier/day)

The Supplier Warehouse USA worksheet can be used to delete USAs at the SKU / Supplier / Day level or to view the effect of deletions of Store USAs for stores sourced by this supplier.

Deleting a Supplier USA deletes all store USAs sourced by this Supplier /Day combination.

When a Store USA(s) is deleted, the Supplier USA is updated to reflect the lower level changes.

Delete Supplier USA Worksheet

The following measures appear automatically when using the default template.

Measure Label	Description
USA Delete Allocation at Supplier	The USA Delete Allocation is checked to delete all store USAs sourced by this supplier /Day combination. The Store Allocation Type will be changed to "Delete" and the Store User Specified Allocation will be cleared for these stores.
USA Supplier Allocation Type	The USA Supplier Allocation Type is the allocation type of this SKU for all stores in the workbook sourced by this supplier. If the values are different, a question mark (?) will be displayed. If the Allocation Type is not "unavailable", Valid values are: - None - Add - Replace - Delivery Window The Supplier Allocation Type may be updated based on deletions of Store User Specified Allocations. (Read only)
USA Supplier Summary	The USA Supplier Summary displays the sum of all store USAs sourced by this Supplier /Day combination. If a store USA sourced by this supplier is deleted, the supplier User Specified Allocation Calculation is updated by subtracting the Store USA quantity from the Supplier USA quantity. (Read only)

Build Workbooks

Set Up Workbooks for Automatic Builds

Typically, the SRP workbooks are automatically built during the nightly batch run by using workbook-creation settings that are defined by system administrators.

The Workbook Auto Build feature allows users to set up workbook builds to take place on a regular basis during nightly batch runs. Workbooks to be built in this way are added to the auto build queue. Because the workbook build process is automated, users are spared the processing time required to regularly enter the same wizard selections each time a new workbook is built. And because the build process occurs overnight, users are spared the wait time associated with constructing new workbooks.

The Workbook Auto Build feature works through the Workbook Auto Build Maintenance Wizard.

Build Automatic Workbook

1. Click **New** on the toolbar, or choose File – New. The New dialog box is displayed.
2. On the Administration tab, select Workbook Auto Build Maintenance.
3. Click **OK**. The Workbook Auto Build Maintenance Wizard is displayed.
4. From the task list, select **Add a Workbook**.
5. Click **Next**.
6. Select a workbook template type
7. Click **Next**.
8. If you are a system administrator, you are now prompted to specify the owner of the new workbook. Select **Administrator** or **Default User**.
9. Click **Next**.

Note: If you are not a system administrator, the system assigns the new workbook to you by default, so this window will not appear.

10. Fill in the workbook name (Build Label), the frequency (in days) with which the workbook should be built (Build Frequency), and the next date that the workbook should be built (Next Build Date).
11. Select one of the following radio buttons to specify access privileges for this workbook:
 - User – allows only you to access and make changes to the workbook
 - World – permits any user to make changes to the workbook
 - Group – allows only those users who are in your group (as determined by your System Administrator) to make changes to the workbook

12. Select the group that owns the workbook. You can choose from the list of groups to which you belong.
13. Click **Next** to initialize the wizard for the workbook template selected in step 6 above. This wizard guides you through the process of building the workbook. For detailed information about building specific SRP workbooks, see “Chapter 3 – Workbook and Worksheet Descriptions”.
14. Click **Finish**. The workbook is added to the queue of workbooks that were automatically built during batch processing.

Build a Workbook Manually

Workbooks can also be manually built by using the workbook-creation wizards. The wizards include several screens where you specify the scope of the data to be included in the workbook; such as selecting positions on the Time, Product, and Location hierarchies. The specific questions that a wizard asks may differ depending on the type of workbook that you are building, but the basic purpose of wizards of this type are to allow you to select specific data to be incorporated into your new workbook. Once you make these selections and complete the workbook creation; the workbook is built, opened, and displayed in the solution.

Note: Depending on the amount of days, products, and stores that you have chosen to include in the plan, the workbook creation process can happen quickly or it can take a significant amount of time.

Build Manual Workbook

1. From the main menu, select **File – New**, or Click **New** from the toolbar. The New dialog box is displayed.
2. Select the **SRP** tab.
3. Select the workbook type from the list of workbook templates.
4. The wizard for the selected workbook template steps you through the process of building the new workbook. For detailed information about building specific SRP workbooks, see “Chapter 3 – Workbook and Worksheet Descriptions”.

Calculations

The calculation of the Store Receipt Plan is performed during the AIP batch process runs. This process produces SRP and WRP receipt plans. This section concentrates on the calculations as they apply to SRP.

Replenishment

Replenishment is an AIP batch process that runs twice within the nightly batch. It calculates the replenishment plan for each SKU-pack size at each store across the planning horizon. Replenishment assumes no quantity constraints and so the orders calculated for the stores reflect their need without regard for the ability of the source of the orders (warehouse or supplier) to supply them.

However, real world constraints upon the supply of product do exist. This is addressed by splitting the planning horizon for each SKU-pack size/Store into two distinct periods of time. The first period contains that part of the planning horizon over which constraints will apply. This is referred to as the fixed period – because the ultimate supply of stock within this time period is limited – or fixed. The second period of time is simply called “Post Fixed Period” and refers to that remaining part of the planning horizon that exists after the fixed period.

A special case of replenishment is when a SKU is capped. The Inventory Cap represents a physical space constraint in units at a store for a given day. The Inventory Capping functionality generates a Store replenishment plan such that inventory (including planned receipts, expected receipts, and current inventory) at the store does not violate the space constraints at the store for any day. At the same time, the Warehouse replenishment plans are generated based on forecasted demand from the stores that have no inventory caps being applied to it across time.

Replenishment is run twice in each night – the first time it produces a replenishment plan for the fixed period for all valid SKU-pack/Store. The second time it produces a replenishment plan for the Post Fixed Period for all valid SKU-pack/Store. In between these 2 replenishment runs, the constraints that relate to the fixed period for each SKU-pack/Store are applied. These constraints modify the plan within the fixed period and ultimately determine the correct inventory position at the start of the post fixed period. This updated inventory position is then used by the second run of the replenishment process.

Replenishment looks at the current inventory position, forecasted demand, customer orders, and expected receipts to project the inventory position in the future. Based on the user-defined Replenishment Method and other user-defined parameters, stocking level targets (allocation boundaries) for a product/store combination are calculated and used in generating an ideal receipt plan that is not limited by available inventory constraints.

Replenishment Calculations Variables

Fixed Period

The term Fixed Period refers to the period of time for a location inside which the supply of inventory for a SKU-Pack is ultimately constrained – or fixed.

Typically, the only time AIP assumes infinite availability of supply is when the store's source is a supplier. In a multi-tier supply chain, the fixed period for a store is the time period it takes for an order to be delivered from a supplier, and pass through the appropriate levels of the supply chain to reach the store.

The time it takes a product to be moved from one location to another is the lead-time. The fixed period for a given SKU-pack/Store is the sum of the lead times for all locations an order must pass through from Supplier to the store.

ATP Dates

Not everyday in the planning horizon is a legitimate delivery day for a store to receive an order for a SKU-pack. Legitimate delivery days are referred to as Available to Plan (ATP) days and are specific to a particular SKU-pack and location. Replenishment only plans order quantities for receipt on ATP days.

Review Time

Review time describes the period of time which is assessed to determine an order quantity for a specific ATP day. Review time is the number of days between one day and the next delivery day. The first day of the Review Time is the ATP day, referred to as the Beginning of Review Time (BRT). The last day of the Review Time is referred to as the End of Review Time (ERT). The ERT for any ATP day is defined as the day before the BRT of the next ATP day.

The Review Time for a particular ATP day is considered to be all the days between, and including, the BRT and ERT. Therefore, if BRT and ERT fall on the same day, the Review Time is considered to be 1 day.

Forecasted Demand over Review Time

A necessary pre-requisite for performing replenishment for a store is a Forecast Demand stream. Forecasted demand is passed to AIP from an external forecasting system.

When calculating allocation boundaries, forecasted demand summed over the review time is considered.

Calculation Expressions:

FD = Forecasted Demand

FDRT = Forecasted Demand over Review Time

BRT = Beginning of Review Time

ERT = End of Review Time

$$FDRT = \sum_{(BRT)}^{(ERT)} FD$$

Customer Orders over Review Time

Customer orders are orders placed by Customers at a store for a specific quantity of a SKU for collection on a specific delivery date. The acceptance of a customer order at a store is usually accompanied with a binding agreement that commits the store to meeting the order – over and above any other forecast of demand. This means that customer orders are treated as additional demand – on top of normal forecasted demand.

When calculating a planned receipt, customer orders summed over the review time are considered. Customer Orders must always arrive into the store at least a day before the actual day of demand, but even earlier if RALT is greater than 1, so when summing Customer Orders over the review time (CORT), the period of time used is shifted by the Max of 0 and (1-RALT).

Calculation Expressions:

CO = Customer Orders

CORT = Customer Orders over Review Time

BRT = Beginning of Review Time

ERT = End of Review Time

Calculation:

$$CORT = \frac{(ERT + \text{Max}(0, 1 - RALT_{(\text{next ATP day})}))}{(BRT + \text{Max}(0, 1 - RALT_{\text{current ATP day}}))} \sum CO$$

Expected Receipts over Review Time

Expected Receipts are those orders (Purchase Orders or Transfers) that have already been executed and therefore need to be considered when planning future orders for a store. Expected Receipts contain quantities of a specific SKU-pack due to arrive at a destination on a specified day.

Expected Receipts consist of two types of orders:

- On Orders represent those orders which have been executed, but as of yet there is no information regarding their physical shipment to the destination.
- In Transits represent those orders which have physically shipped to the destination.

Calculation Expressions:

For a given SKU-pack/Destination/Delivery Date

ER = Expected Receipts

IT = In Transits

OO = On Orders

Calculation:

$$ER = IT + OO$$

Calculation Expressions:

When calculating a planned receipt, expected receipts summed over the review time are considered.

ER = Expected Receipts

ERRT = Expected Receipts over Review Time

BRT = Beginning of Review Time

ERT = End of Review Time

$$ERRT = \sum_{(BRT)}^{(ERT)} ER$$

Product Life

Product Life (PL) refers to a number of days of life a product has upon receipt at a store. Once a product expires after a specified number of days, it can no longer be used to meet sales. The day of receipt at store is considered one day of a product's life so a product will expire at the end of (the day of receipt + PL – 1 day).

Expected Spoilage

Expected Spoilage (ES) refers to a quantity of a SKU at a store whose product life expires and therefore becomes un-sellable at the end of a day. Expired quantities can not be used for any sales after the day they expire.

Expected Spoilage is calculated for Current inventory and Planned or Expected receipts when the Expected Spoilage Calculation Indicator is set to true. All inventory arriving at a store as part of PR or ER is assumed to have full product life. Any remaining part of the receipt not used to fulfill demand will spoil on (Day of receipt + Product Life – 1).

Inventory Capping and Store Available Space

The primary drivers of Inventory Capping functionality are as follows:

- Cost of exceeding store capacity is significantly higher than any potential missed sales because of no stock at store. Thus the plan should never exceed the capacity constraint in terms of the inventory that a store can carry on any given day
- Store sources (warehouses) should still generate orders (if required) as if there was no capping at the store at all.

When managing to inventory caps, space is at a premium and overstocks within the store are costly and labor intensive to manage. As such, when replenishing, a receipt plan should be generated keeping in mind that it should not violate the capacity constraints at the store for any day. This is achieved by calculating an 'Available Space' quantity for any given ATP day. The AIP processing logic ensures that the URP is never greater than the Available Space. Available Space is calculated (and hence Inventory Capping functionality is applied) for all SKUs that have the Capping Flag set to 'YES'. This functionality is applied at a SKU/Store/Day level.

Because the store space is limited, to ensure that shipments will not go over the SKU cap at a store, it is assumed that the forecasted sales will not be realized over the execution window. The execution window represents the point in time when the order would have to be executed upon. This day is the "Order Day," which is the lead time number of days earlier than the ATP day. The lead time in question is the lead time on the ATP day.

Also, any expected receipts over the planning horizon starting from the ATP day onwards, since they have already been committed, would be considered as taking up space as of the ATP day. In other words, space is reserved for them; hence we cannot use that space to plan for extra receipts on the ATP day.

The Store Available Space calculation has the following characteristics:

- Calculated only on ATP days
- Maximum value cannot exceed the SKU Cap for the ATP day
- Store Available Space is the SKU Cap on the ATP day minus
 - Projected Inventory on the Order Day (day which is lead time (on the ATP day) days prior to the ATP day)
 - Sum of Expected Receipts from the Order Day across the planning horizon
 - Sum of Planned Receipts (if any) from the Order Day till the ATP day
 - If store available space is negative, it is set to zero.

Calculation Expressions:

t = any ATP day

$SAS(t)$ = Store Available Space on the ATP day

$SKUCap(t)$ = SKU Cap on the ATP day

$LT(t)$ = Lead time on the ATP day

$PI(t-LT(t))$ = PI on the Order Day for day t

ER = Expected Receipts

PR = Planned Receipts (URP at the time of replenishment/CRP at the time of reconciliation etc.)

Calculations:

$$SAS(t) = \text{Max}(SKUCap(t) - PI(t-LT(t)) - \sum_{t-LT(t)}^{t-1} PR - \sum_{t-LT(t)}^{\text{EndOfPlanHzn}} ER, 0)$$

Note: SAS is first calculated during the replenishment (prior to capping) run and is updated as the PI and PR are updated during processing. The SAS calculated during capped replenishment still represents the most constrained available space, since the PR (and hence PI) can only be constrained further during reconciliation.

Since valid ATP days include only those days on which it is possible to receive products for a shipment day on Today or in the future, $t-LT(t)$ for an ATP day would always be a day in the planning horizon.

Allocation Boundaries

The basis for replenishment is the calculation of allocation boundaries. These boundaries represent varying levels of inventory required to satisfy particular requirements. The calculation of these boundaries varies significantly across the replenishment methods. The allocation boundaries are as follows:

- **Minimum Sales Stock**
The Minimum Sales Stock (MSS) represents the minimum stock level that a SKU requires at a store to satisfy sales forecasts and customer orders, and achieve a projected inventory of 0 at the end of the review time period.
- **Safety Stock**
Safety Stock (SS) is the amount of stock that should be kept on hand in an effort to mitigate the risk of out of stocks due to forecast variability.
- **Receipt Point**
The Receipt Point (RP) represents the inventory level below which an order should be triggered.
- **Receive Up To Level**
The Receive Up To Level (RUTL) denotes the target level of inventory when generating an order.
- **Maximum Sellable Quantity**
The Maximum Sellable Quantity (MSQ) represents the level of inventory that can be sold within the life of a product.

Allocation Boundaries Calculations Variables

Safety Stock Minimums and Maximums

For replenishment methods that do not calculate Safety Stock based upon Sales, Safety Stock Minimums and Maximums provide a means of applying boundaries to limit the minimum and maximum values for calculated Safety Stock (SS). Before the boundaries can actually be applied to the calculated SS, the upper and lower boundaries themselves need to be determined. The calculation of the minimums and maximums do not vary by replenishment method.

The user may specify upper and lower limits, both in terms of numbers of days and numbers of units. Given that the upper and lower limits may be applied in both units and numbers of days at the same time, the following rules are used to determine which takes priority.

- The lower limit to be applied to SS is simply calculated as the larger of either of the 2 specified Min values in units. That is the smaller of either the Min Units or the Min Days (converted into units).
- The upper limit to be applied to SS is simply calculated as the larger of either of the two specified Max values in units. That is the larger of either the Max Units or the Max Days (converted into units).
- When neither the MinUnits nor Min Days measure has been specified by the user, the lower bound to be applied to SS is zero.
- When neither the MaxUnits nor Max Days measure has been specified by the user, there is no upper boundary to be applied to SS.
- Where the calculated lower boundary for SS exceeds the calculated upper boundary for SS, the lower boundary should be set to the upper boundary.

It is necessary to convert the Min and Max Day values into units so that they can be directly compared to the user specified Min and Max Unit values. Both the min and max day values, when specified, can be converted into units by summing the specified number of days of forecast demand commencing (and including) the Beginning of Review Time (BRT).

The following logic summarizes the processing for stores. SS MAX and SS MIN refer to the ultimate maximum and minimum boundaries to be applied to store safety stock.

If the SS MIN value exceeds the SS MAX value, then the Minimum value is set to the Maximum value.

Safety Stock Minimum

Calculation Expressions:

SSMIN = Safety Stock Minimum

SSMinUnits = Safety Stock Minimum Units (user-defined parameter)

SSMinDays = Safety Stock Minimum Days (user-defined parameter)

FD = Forecasted Demand

BRT = Beginning of Review Time

ERT = End of Review Time

Calculation:

$$SSMIN = \text{Max} \left(SSMinUnits, \sum_{BRT}^{(BRT + SSMinDays - 1)} FD \right)$$

Safety Stock Maximum

Calculation Expressions:

SSMAX = Safety Stock Maximum

SSMaxUnits = Safety Stock Maximum Units (user-defined parameter)

SSMaxDays = Safety Stock Maximum Days (user-defined parameter)

FD = Forecasted Demand

BRT = Beginning of Review Time

ERT = End of Review Time

Calculation:

$$SSMAX = \text{Max} \left(SSMaxUnits, \sum_{BRT}^{(BRT + SSMaxDays - 1)} FD \right)$$

Weekly Sales Min and Weekly Sales Max

There are two methods that calculate safety stock based upon sales. These methods are Factor AWS and Sales Week Range. For these methods safety stock ranging boundaries mentioned above are not used. Instead, the calculated safety stock is limited by two user specified boundaries - Weekly Sales Min and Weekly Sales Max.

If the Weekly Sales Min value exceeds the Weekly Sales Max value, then the Minimum value is set to the Maximum value.

Supplier Compliance Safety Stock

The purpose of Supplier Compliance Safety Stock Uplift (SCSSU) is to address the poor record of a supplier for meeting their delivery obligations. The calculation of SCSSU involves summing demand for a period of time specified by the user as a number of days, Supplier Compliance Safety Stock Days (SCSSD). The beginning of the period over which the summation should take place is calculated as the current ATP day plus an additional number of days. This additional number of days is the maximum of the number of days in the review time for the current ATP day or the user-specified Inventory Selling Days (ISD) parameter.

Calculation Expressions:

SCSSU = Supplier Compliance Safety Stock Uplift

SCSSD = Supplier Compliance Safety Stock Days (user-defined parameter)

FD = Forecasted Demand

RT = Review Time

ISD = Inventory Selling Days (user-defined parameter)

Calculations:

$$StartDate = currentATPday + \text{Max}(RT, ISD)$$

$$SCSSU = \sum_{StartDate}^{StartDate+SCSSD-1} FD$$

Boundary Stock

Boundary Stock (BS) is a means of including other promotion and presentation factors in addition to Safety Stock (SS) when considering the stock level at which an order is generated and how much stock to carry over and above demand.

Calculation Expressions:

PS = Presentation Stock

PPS = Promotional Presentation Stock

SS = Safety Stock

Calculations:

Based on the Boundary Stock Identifier (user-defined parameter), Boundary Stock is determined below:

Max (SS, PS + PPS)

Max (SS, PS)

Max (SS, PPS)

SS + PS + PPS

SS + PS

SS + PPS

SS

All BS Identifiers are available for all Replenishment methods.

Replenishment Methods Used in SRP

There are a number of replenishment methods that may be used to generate a replenishment plan in SRP. The different methods are appropriate for different kinds of situations.

The replenishment method that is used for a particular SKU or set of SKUs is typically chosen during implementation by SRP super users who set the replenishment parameters. This method is used throughout the supply chain management process. The use of the replenishment method is monitored for effectiveness, and it is modified as needed over time.

The following replenishment methods can be used in SRP:

- Min/Max
- Time Supply
- Dynamic
- Hybrid
- No Replenishment
- Poisson Replenishment
- Loaded SS Dynamic
- Sales Week Range
- Factor AWS

The following sections discuss these replenishment methods, which includes an explanation of the allocation boundaries calculations.

Min/Max Replenishment Method

Min/Max is a simple, non-forecast-based replenishment method. It is generally used in the following types of situations:

- When it is impossible to generate a reasonable forecast, such as a completely new type of product that cannot be modeled after anything else
- For extremely slow-selling items where the minimum presentation levels constantly exceed the weekly demand

Minimum Sales Stock

The Minimum Sales Stock (MSS) for the Min/Max replenishment method is calculated as the sum of Safety Stock and Customer Orders over the review time.

Calculation Expressions:

MSS = Minimum Sales Stock

SS = Safety Stock

CORT = Customer Orders over Review Time

MSQ = Maximum Sellable Quantity

SC = Shelf Capacity

Calculation:

Calculated MSS may not exceed Maximum Sellable Quantity (MSQ). Where it does, MSS is set to MSQ.

$$MSS = \text{Min}(SS + CORT, MSQ)$$

When the product/store is constrained by shelf capacity (Shelf Capacity Flag is true) the calculated MSS for stores may not exceed the level required to fill the shelf to capacity and meet CORT. Where it does, MSS is set to Shelf Capacity (SC) + CORT.

$$MSS = \text{Min}(MSS, SC + CORT)$$

Safety Stock

Safety Stock in the Min/Max method consists of the minimum supply in units (MinS) multiplied by an increment percentage factor (Inc%).

Minimum stock level (user-defined parameter) is the minimum number of units required to have on hand to satisfy demand.

Increment Percent (user-defined parameter) is a multiplier for minimum and maximum stock that is designed to handle temporary fluctuation in demand for items on Min/Max replenishment without altering the established MIN and MAX values.

Calculation Expressions:

SS = Safety Stock

MinS = Minimum stock

Inc% = Increment Percent

SCSSU = Supplier Compliance Safety Stock Uplift

Calculation:

$$SS = (\text{MinS} * \text{Inc}\%) + \text{SCSSU}$$

Receipt Point

Receipt Point in the Min/Max method is set to the calculated Boundary Stock (BS).

Next, Customer Orders (CORT) and Demo Stock (DS) must be added to the previously-calculated RP. However, the value may not exceed the sum of MSQ plus Demo Stock.

Finally, when the product/store is constrained by shelf capacity (Shelf Capacity Flag is true), the current RP value is compared to the sum of Shelf Capacity (SC), CORT and Demo Stock. RP is set to the lesser of the two.

Calculation Expressions:

RP = Receipt Point

BS = Boundary Stock

CORT = Customer Orders over Review Time

DS = Demo Stock (user-defined parameter)

MSQ = Maximum Sellable Quantity

SC = Shelf Capacity (user-defined parameter)

Calculation:

$$RP = BS$$

Add CORT and Demo Stock and check the value does not exceed MSQ, constraining by shelf capacity when relevant.

When Shelf Capacity is not relevant for the SKU

$$RP = \text{Min}(BS + CORT + DS, MSQ + DS)$$

When Shelf Capacity is relevant for the SKU

$$RP = \text{Min}(\text{Min}(BS + CORT + DS, MSQ + DS), SC + CORT + DS)$$

Receive Up To Level

For the Min/Max replenishment method, Receive Up To Level (RUTL) is calculated by taking the max of Boundary Stock (BS) and the product of the Maximum Stock (MaxS) and Increment Percent (Inc %) values.

Next, Customer Orders (CORT) and Demo Stock (DS) must be added to the previously-calculated RUTL. However, the value may not exceed the sum of MSQ plus Demo Stock.

Finally, when the product/store is constrained by shelf capacity (Shelf Capacity Flag is true), the current RUTL value is compared to the sum of Shelf Capacity (SC), CORT and Demo Stock. RUTL is set to the lesser of the two.

Calculation Expressions:

RUTL = Receive Up To Level

PRUTL = Preliminary Receive Up To Level

BS = Boundary Stock

MaxS = Maximum stock

Inc% = Increment Percent

CORT = Customer Orders over Review Time

DS = Demo Stock (user-defined parameter)

MSQ = Maximum Sellable Quantity

SC = Shelf Capacity (user-defined parameter)

Calculation:

$$PRUTL = \text{Max}(\text{MaxS} * \text{Inc}\%, BS)$$

Add CORT and Demo Stock and check the value does not exceed MSQ, constraining by shelf capacity when relevant.

When Shelf Capacity is not relevant for the SKU

$$RUTL = \text{Min}(PRUTL + CORT + DS, MSQ + DS)$$

When Shelf Capacity is relevant for the SKU

$$RUTL = \text{Min}(\text{Min}(PRUTL + CORT + DS, MSQ + DS), SC + CORT + DS)$$

Maximum Sellable Quantity

For the Min/Max replenishment method, Maximum Sellable Quantity (MSQ) is calculated as the sum of forecasted demand over the product life starting from the beginning of the review time and Customer Orders over Review Time.

MSQ is dependent upon Product Life (PL) and the MSQ Constraint Indicator. Where Product Life is deemed to be not relevant for a SKU and/or the MSQ Constraint Indicator is "FALSE", the MSQ is considered infinite (Unbounded).

Calculation Expressions:

MSQ = Maximum Sellable Quantity

FD = Forecasted Demand

CORT = Customer Orders over Review Time

PL = Product Life

BRT = Beginning of Review Time

Calculation:

When product life is not relevant for the SKU and/or the MSQ Constraint Indicator = False

$$MSQ = \text{unbounded}$$

When product life is relevant for the SKU and the MSQ Constraint Indicator = True

$$MSQ = \sum_{BRT}^{\text{Current ATP day} + (PL - 1)} FD + CORT$$

Time Supply Replenishment Method

The Time Supply replenishment method allows the user to maintain a minimum and maximum amount of stock in terms of days of supply.

The Time Supply Horizon Parameter

The Time Supply Horizon parameter is an optional parameter used in safety stock and receive up to level calculations for this method. A projected daily average rate of sale is calculated based on the forecasted demand over the time supply horizon. This parameter can be used to smooth spiky forecasts or extend the time supply days beyond the planning horizon.

If the Time Supply Horizon parameter is undefined, the total of the forecast over the minimum and maximum time supply days is used instead. This results in a truer calculation of the demand since the forecasted demand over the minimum supply days and maximum supply days may have varying rates of sale.

Minimum Sales Stock

The Minimum Sales Stock (MSS) for the Time Supply replenishment method is calculated as the sum of Safety Stock and Customer Orders over the review time.

Calculation Expressions:

MSS = Minimum Sales Stock

SS = Safety Stock

CORT = Customer Orders over Review Time

MSQ = Maximum Sellable Quantity

SC = Shelf Capacity (user-defined parameter)

Calculation:

Calculated MSS may not exceed Maximum Sellable Quantity (MSQ). Where it does, MSS is set to MSQ.

$$MSS = \text{Min}(SS + CORT, MSQ)$$

When the product/store is constrained by shelf capacity (Shelf Capacity Flag is true) the calculated MSS for stores may not exceed the level required to fill the shelf to capacity and meet CORT. Where it does, MSS is set to Shelf Capacity (SC) + CORT.

$$MSS = \text{Min}(MSS, SC + CORT)$$

Safety Stock

Safety Stock (SS) in the Time Supply method consists of calculating a stock level based on the forecasted demand or an average rate of sales.

If a Time Supply Horizon (TSH) has been specified, then this method establishes an Average Rate of Sale (ROS) over the time supply horizon period starting (and including) the beginning of review time. This average is then multiplied by the Minimum Time Supply Days (MinTS).

If a time supply horizon is not specified, then the method sums the forecasted demand over the Minimum Time Supply Days (MinTS) starting with (and including) the beginning of the review time.

The result of either of the calculations above is then checked to ensure that it falls between the SSMIN and SS MAX boundaries determined in the Safety Stock Minimums and Maximums section. Finally, the user-defined safety stock level factor (SSLF) is added.

Calculation Expressions:

SS = Safety Stock

TSH = Time Supply Horizon (user-defined parameter)

FDMIN = Forecast Minimum

FD = Forecasted Demand

MinTS = Minimum Time Supply Days (user-defined parameter)

SSMIN = Safety Stock Minimum

SSMAX = Safety Stock Maximum

SSLF = Safety Stock Lift Factor (user-defined parameter)

ROS = Rate of Sale

SCSSU = Supplier Compliance Safety Stock Uplift

BRT = Beginning of Review Time

ERT = End of Review Time

Calculations:

When the time supply horizon has been specified (TSH>0)

$$ROS = \frac{\sum_{BRT}^{(BRT+TSH-1)} FD}{TSH}$$

$$FDMIN = ROS * MinTS$$

When the time supply horizon has not been specified (TSH=0)

$$FDMIN = \frac{\sum_{BRT}^{BRT+MinTS-1} FD}{MinTS}$$

In either case,

$$SS = \text{Max}(\text{Max}(\text{Min}(FDMIN, SSMAX), SSMIN) + SSLF, 0)$$

Note: If SSMIN exceeds SSMAX, then SSMIN is set to SSMAX.

Finally, Supplier Compliance Safety Stock Uplift is added to the calculated safety stock.

$$SS = SS + SCSSU$$

Receipt Point

Receipt Point in the Time Supply method is set to the calculated Boundary Stock (BS).

Calculation Expressions:

RP = Receipt Point

BS = Boundary Stock

CORT = Customer Orders over Review Time

DS = Demo Stock (user-defined parameter)

MSQ = Maximum Sellable Quantity

SC = Shelf Capacity (user-defined parameter)

Calculations:

$$RP = BS$$

Add CORT and Demo Stock and check the value does not exceed MSQ, constraining by shelf capacity when relevant.

When Shelf Capacity is not relevant for the SKU

$$RP = \text{Min}(BS + CORT + DS, MSQ + DS)$$

When Shelf Capacity is relevant for the SKU

$$RP = \text{Min}(\text{Min}(BS + CORT + DS, MSQ + DS), SC + CORT + DS)$$

Receive Up To Level

Receive Up To Level (RUTL) in the Time Supply method consists of calculating a target stock level used in generating an order based on the forecasted demand or an average rate of sales.

If a Time Supply Horizon (TSH) has been specified, then this method establishes an Average Rate of Sale (ROS) over the time supply horizon period starting (and including) the beginning of review time. This average is then multiplied by the Maximum Time Supply Days (MaxTS).

If a time supply horizon is not specified, then the method sums the forecasted demand over the Maximum Time Supply Days (MaxTS) period starting (and including) the beginning of the review time.

The result of either of the calculations above is added to the safety stock level factor (SSLF). It is then compared against the Boundary Stock with the larger becoming the RUTL.

Next, Customer Orders (CORT) and Demo Stock (DS) must be added to the previously-calculated RUTL. However, the value may not exceed the sum of MSQ plus Demo Stock.

Finally, when the product/store is constrained by shelf capacity (Shelf Capacity Flag is true), the current RUTL value is compared to the sum of Shelf Capacity (SC), CORT and Demo Stock. RUTL is set to the lesser of the two.

Calculation Expressions:*RUTL = Receive Up To Level**PRUTL = Preliminary Receive Up To Level**TSH = Time Supply Horizon (user-defined parameter)**FDMAX = Forecast Maximum**FD = Forecasted Demand**MaxTS = Maximum Time Supply Days (user-defined parameter)**ROS = Rate of Sale**SSLF = Safety Stock Lift Factor (user-defined parameter)**BS = Boundary Stock**CORT = Customer Orders over Review Time**DS = Demo Stock (user-defined parameter)**MSQ = Maximum Sellable Quantity**SC = Shelf Capacity (user-defined parameter)**BRT = Beginning of Review Time**ERT = End of Review Time*Calculations:

Calculate the maximum demand (FDMAX) based on the time supply horizon.

When the time supply horizon has been specified (TSH>0)

$$ROS = \frac{\sum_{BRT}^{(BRT+TSH-1)} FD}{TSH}$$

$$FDMAX = ROS * MaxTS$$

When the time supply horizon has not been specified (TSH=0)

$$FDMAX = \sum_{BRT}^{BRT+MaxTS-1} FD$$

Calculate the PRUTL based on FDMAX.

$$PRUTL = Max(FDMAX + SSLF, BS)$$

Add CORT and Demo Stock and check the value does not exceed MSQ, constraining by shelf capacity when relevant.

When Shelf Capacity is not relevant for the SKU

$$RUTL = Min(PRUTL + CORT + DS, MSQ + DS)$$

When Shelf Capacity is relevant for the SKU

$$RUTL = Min(Min(PRUTL + CORT + DS, MSQ + DS), SC + CORT + DS)$$

Maximum Sellable Quantity

For the Time Supply replenishment method, Maximum Sellable Quantity (MSQ) is calculated as the sum of forecasted demand over the product life starting from the beginning of the review time and Customer Orders over Review Time.

MSQ is dependent upon Product Life (PL) and the MSQ Constraint Indicator. Where Product Life is deemed to be not relevant for a SKU and/or the MSQ Constraint Indicator is 'FALSE', the MSQ is considered infinite (Unbounded).

Calculation Expressions:

MSQ = Maximum Sellable Quantity

FD = Forecasted Demand

CORT = Customer Orders over Review Time

PL = Product Life

BRT = Beginning of Review Time

Calculations:

When product life is not relevant for the SKU and/or the MSQ Constraint Indicator = False

$$MSQ = \text{unbounded}$$

When product life is relevant for the SKU and the MSQ Constraint Indicator = True

$$MSQ = \sum_{BRT}^{\text{Current ATP day} + (PL - 1)} FD + CORT$$

Dynamic Replenishment Method

The goal of the Dynamic replenishment method is to replenish only the quantity required to meet user specified customer service level. It is a statistical method that assumes the forecast demand observes normal distribution. The dynamic method minimizes the amount of safety stock on hand while meeting specified service levels. Higher service levels will result in higher levels of safety stock. Forecast accuracy is also important for this method. Products with high standard deviations will require more stock to cover the deviations.

Minimum Sales Stock

The Minimum Sales Stock (MSS) for the Dynamic replenishment method is calculated as the sum of Forecasted Demand and Customer Orders over the review time.

Calculation Expressions:

MSS = Minimum Sales Stock

SS = Safety Stock

CO = Customer Orders

CORT = Customer Orders over Review Time

MSQ = Maximum Sellable Quantity

SC = Shelf Capacity (user-defined parameter)

Calculations:

Calculated MSS may not exceed Maximum Sellable Quantity (MSQ). Where it does, MSS is set to MSQ.

$$MSS = \text{Min}((\sum_{BRT}^{ERT} FD + CO), MSQ)$$

When the product/store is constrained by shelf capacity (Shelf Capacity Flag is true) the calculated MSS for stores may not exceed the level required to fill the shelf to capacity and meet CORT. Where it does, MSS is set to Shelf Capacity (SC) + CORT.

$$MSS = \text{Min}(MSS, SC + CORT)$$

Safety Stock

Dynamic Safety Stock (SS) is a statistical method that assumes the forecast demand observes normal distribution. The first step is to determine the acceptable unit loss (AUL) (also referred to as Expected Units Short). This refers to the acceptable amount of stock outs for a given product based on the specified service level over the review time and is calculated as shown below.

Calculation Expressions:

SS = Safety Stock

AUL = Acceptable Unit Loss

SL = Store Service Level (user-defined parameter)

σ = Standard Deviation Over Review Time

FDRT = Forecasted Demand over Review Time

SSS = Statistical Safety Stock

SSMIN = Safety Stock Minimum

SSMAX = Safety Stock Maximum

SSLF = Safety Stock Lift Factor (user-defined parameter)

SCSSU = Supplier Compliance Safety Stock Uplift

RT = Review Time

BRT = Beginning of Review Time

ERT = End of Review Time

Calculations:

$$AUL_{RT} = \frac{(1 - SL) * FDRT}{\sigma}$$

A standard lookup function using a normal distribution table is then used to determine a factor which is multiplied by the standard deviation (over review time). The acceptable unit loss (AUL) over the review time is used to find the Z-factor needed for the Statistical Safety Stock Calculation. The result of the lookup is multiplied by the lead time deviation to determine the statistical safety stock.

$$SSS = \text{LookupFunction}(AUL_{RT}) * \sigma$$

The result is then checked to ensure that it falls between the SSMIN and SS MAX boundaries determined in the safety stock range section. Finally, the safety stock level factor (SSLF) is added and the result is checked to ensure that it does not drop below zero.

$$SS = \text{Max}(\text{Max}(\text{Min}(SSS, SS MAX), SSMIN) + SSLF, 0)$$

Finally, Supplier Compliance Safety Stock Uplift is added to the calculated safety stock.

$$SS = SS + SCSSU$$

Receipt Point

Receipt Point in the Dynamic method is calculated as the sum of forecasted demand over the review time plus Boundary Stock (BS).

Calculation Expressions:

RP = Receipt Point

PRP = Preliminary Receipt Point

BS = Boundary Stock

FDRT = Forecasted Demand over Review Time

CORT = Customer Orders over Review Time

DS = Demo Stock (user-defined parameter)

MSQ = Maximum Sellable Quantity

SC = Shelf Capacity (user-defined parameter)

Calculations:

$$PRP = FDRT + BS$$

Add CORT and Demo Stock and check the value does not exceed MSQ, constraining by shelf capacity when relevant.

When Shelf Capacity is not relevant for the SKU

$$RP = \text{Min}(PRP + CORT + DS, MSQ + DS)$$

When Shelf Capacity is relevant for the SKU

$$RP = \text{Min}(\text{Min}(PRP + CORT + DS, MSQ + DS), SC + CORT + DS)$$

Receive Up To Level

For Receive Up To Level (RUTL) using the Dynamic replenishment method, demand is assessed over a number of days. This number of days is the larger of either the number of days in the review time, or the user-specified inventory selling days (ISD).

The RUTL is then calculated as the sum of demand over the calculated number of days commencing with the beginning of the review time. Boundary stock (BS) and safety stock level factor (SSLF) are then added.

Next, Customer Orders (CORT) and Demo Stock (DS) must be added to the previously-calculated RUTL. However, the value may not exceed the sum of MSQ plus Demo Stock.

Finally, when the product/store is constrained by shelf capacity (Shelf Capacity Flag is true), the current RUTL value is compared to the sum of Shelf Capacity (SC), CORT and Demo Stock. RUTL is set to the lesser of the two.

Calculation Expressions:

RUTL = Receive Up To Level

PRUTL = Preliminary Receive Up To Level

ND = Number of Days

ISD = Inventory Selling Days (user-defined parameter)

FD = Forecasted Demand

SSLF = Safety Stock Lift Factor (user-defined parameter)

BS = Boundary Stock

CORT = Customer Orders over Review Time

DS = Demo Stock (user-defined parameter)

MSQ = Maximum Sellable Quantity

SC = Shelf Capacity (user-defined parameter)

BRT = Beginning of Review Time

ERT = End of Review Time

Calculations:

$$ND = \text{Max}(ERT - BRT + 1, ISD)$$

$$PRUTL = \sum_{BRT}^{BRT + ND - 1} FD + BS$$

Add CORT and Demo Stock and check the value does not exceed MSQ, constraining by shelf capacity when relevant.

When Shelf Capacity is not relevant for the SKU

$$RUTL = \text{Min}(PRUTL + CORT + DS, MSQ + DS)$$

When Shelf Capacity is relevant for the SKU

$$RUTL = \text{Min}(\text{Min}(PRUTL + CORT + DS, MSQ + DS), SC + CORT + DS)$$

Maximum Sellable Quantity

For the Dynamic replenishment method, Maximum Sellable Quantity (MSQ) is calculated as the sum of forecasted demand over the product life starting from the beginning of the review time and Customer Orders over Review Time.

MSQ is dependent upon Product Life (PL) and the MSQ Constraint Indicator. Where Product Life is deemed to be not relevant for a SKU and/or the MSQ Constraint Indicator is 'FALSE', the MSQ is considered infinite (Unbounded).

Calculation Expressions:

MSQ = Maximum Sellable Quantity

FD = Forecasted Demand

CORT = Customer Orders over Review Time

PL = Product Life

BRT = Beginning of Review Time

Calculations:

When product life is not relevant for the SKU and/or the MSQ Constraint Indicator = False

$$MSQ = \text{unbounded}$$

When product life is relevant for the SKU and the MSQ Constraint Indicator = True

$$MSQ = \sum_{BRT}^{\text{Current ATP day} + (PL - 1)} FD + CORT$$

Hybrid Replenishment Method

The Hybrid replenishment method is a combination of Dynamic and Time Supply replenishment methods. The main difference between the Hybrid and Dynamic methods is the calculation of safety stock. In the Hybrid method, the safety stock is calculated using the same algorithm used in the Time Supply method.

Minimum Sales Stock

The Minimum Sales Stock (MSS) for the Hybrid replenishment method is calculated as the sum of Forecasted Demand and Customer Orders over the review time.

Calculation Expressions:

MSS = Minimum Sales Stock

SS = Safety Stock

CO = Customer Orders

CORT = Customer Orders over Review Time

MSQ = Maximum Sellable Quantity

SC = Shelf Capacity (user-defined parameter)

Calculations:

Calculated MSS may not exceed Maximum Sellable Quantity (MSQ). Where it does, MSS is set to MSQ.

$$MSS = \text{Min}((\sum_{BRT}^{ERT} FD + CO), MSQ)$$

When the product/store is constrained by shelf capacity (Shelf Capacity Flag is true) the calculated MSS for stores may not exceed the level required to fill the shelf to capacity and meet CORT. Where it does, MSS is set to Shelf Capacity (SC) + CORT.

$$MSS = \text{Min}(MSS, SC + CORT)$$

Safety Stock

Safety Stock (SS) in the Hybrid method consists of calculating a stock level based on the forecasted demand or an average rate of sales.

If a Time Supply Horizon (TSH) has been specified, then this method establishes an Average Rate of Sale (ROS) over the time supply horizon period starting (and including) the beginning of review time. This average is then multiplied by the Minimum Time Supply Days (MinTS).

If a time supply horizon is not specified, then the method sums the forecasted demand over the Minimum Time Supply Days (MinTS) starting with (and including) the beginning of the review time.

The result of either of the calculations above is then checked to ensure that it falls between the SSMIN and SS MAX boundaries determined in the Safety Stock Minimums and Maximums section. Finally, the user-defined safety stock level factor (SSLF) is added.

Calculation Expressions:

SS = Safety Stock

TSH = Time Supply Horizon (user-defined parameter)

FDMIN = Forecast Minimum

FD = Forecasted Demand

MinTS = Minimum Time Supply Days (user-defined parameter)

SSMIN = Safety Stock Minimum

SSMAX = Safety Stock Maximum

SSLF = Safety Stock Lift Factor (user-defined parameter)

ROS = Rate of Sale

SCSSU = Supplier Compliance Safety Stock Uplift

BRT = Beginning of Review Time

ERT = End of Review Time

Calculations:

When the time supply horizon has been specified (TSH>0)

$$ROS = \frac{\sum_{BRT}^{(BRT+TSH-1)} FD}{TSH}$$

$$FDMIN = ROS * MinTS$$

When the time supply horizon has not been specified (TSH=0)

$$FDMIN = \sum_{BRT}^{BRT+MinTS-1} FD$$

In either case,

$$SS = \text{Max}(\text{Max}(\text{Min}(FDMIN, SSMAX), SSMIN) + SSLF, 0)$$

Finally, Supplier Compliance Safety Stock Uplift is added to the calculated safety stock.

$$SS = SS + SCSSU$$

Receipt Point

Receipt Point in the Hybrid method is calculated as the sum of forecasted demand over the review time plus Boundary Stock (BS).

Calculation Expressions:

RP = Receipt Point

PRP = Preliminary Receipt Point

BS = Boundary Stock

FDRT = Forecasted Demand over Review Time

CORT = Customer Orders over Review Time

DS = Demo Stock (user-defined parameter)

MSQ = Maximum Sellable Quantity

SC = Shelf Capacity (user-defined parameter)

Calculations:

$$PRP = FDRT + BS$$

Add CORT and Demo Stock and check the value does not exceed MSQ, constraining by shelf capacity when relevant.

When Shelf Capacity is not relevant for the SKU

$$RP = \text{Min}(PRP + CORT + DS, MSQ + DS)$$

When Shelf Capacity is relevant for the SKU

$$RP = \text{Min}(\text{Min}(PRP + CORT + DS, MSQ + DS), SC + CORT + DS)$$

Receive Up To Level

For Receive Up To Level (RUTL) using the Hybrid replenishment method, demand is assessed over a number of days. This number of days is the larger of either the number of days in the review time, or the user-specified inventory selling days (ISD).

The RUTL is then calculated as the sum of demand over the calculated number of days commencing with the beginning of the review time. Boundary stock (BS) and safety stock level factor (SSLF) are then added.

Next, Customer Orders (CORT) and Demo Stock (DS) must be added to the previously-calculated RUTL. However, the value may not exceed the sum of MSQ plus Demo Stock.

Finally, when the product/store is constrained by shelf capacity (Shelf Capacity Flag is true), the current RUTL value is compared to the sum of Shelf Capacity (SC), CORT and Demo Stock. RUTL is set to the lesser of the two.

Calculation Expressions:

RUTL = Receive Up To Level

PRUTL = Preliminary Receive Up To Level

ND = Number of Days

ISD = Inventory Selling Days (user-defined parameter)

FD = Forecasted Demand

BS = Boundary Stock

CORT = Customer Orders over Review Time

DS = Demo Stock (user-defined parameter)

MSQ = Maximum Sellable Quantity

SC = Shelf Capacity (user-defined parameter)

BRT = Beginning of Review Time

ERT = End of Review Time

Calculations:

$$ND = \text{Max}(ERT - BRT + 1, ISD)$$

$$PRUTL = \sum_{BRT}^{BRT + ND - 1} FD + BS$$

Add CORT and Demo Stock and check the value does not exceed MSQ, constraining by shelf capacity when relevant.

When Shelf Capacity is not relevant for the SKU

$$RUTL = \text{Min}(PRUTL + CORT + DS, MSQ + DS)$$

When Shelf Capacity is relevant for the SKU

$$RUTL = \text{Min}(\text{Min}(PRUTL + CORT + DS, MSQ + DS), SC + CORT + DS)$$

Maximum Sellable Quantity

For the Hybrid replenishment method, Maximum Sellable Quantity (MSQ) is calculated as the sum of forecasted demand over the product life starting from the beginning of the review time and Customer Orders over Review Time.

MSQ is dependent upon Product Life (PL) and the MSQ Constraint Indicator. Where Product Life is deemed to be not relevant for a SKU and/or the MSQ Constraint Indicator is 'FALSE', the MSQ is considered infinite (Unbounded).

Calculation Expressions:

MSQ = Maximum Sellable Quantity

FD = Forecasted Demand

CORT = Customer Orders over Review Time

PL = Product Life

BRT = Beginning of Review Time

Calculations:

When product life is not relevant for the SKU and/or the MSQ Constraint Indicator = False

$$MSQ = \text{unbounded}$$

When product life is relevant for the SKU and the MSQ Constraint Indicator = True

$$MSQ = \sum_{BRT}^{\text{Current ATP day} + (PL - 1)} FD + CORT$$

No Replenishment Method

The No Replenishment method is provided for cases when replenishment calculations need to be turned off for a specific SKU/store/day.

This method is used for periods when a store does not want to have any replenishment performed.

Where No Replenishment is used, all allocation boundaries (MSS, SS, RP, RUTL, AND MSQ) are set to zero.

Poisson Replenishment Method

The Poisson replenishment method is identical to the Dynamic replenishment method, except for the way the safety stock is derived. Poisson uses a Poisson distribution lookup table fed by the demand over the review time and the desired service level as parameters. Poisson does not incorporate forecast error.

Required Data

The following data must be loaded in order to use the Poisson replenishment method. Please refer to the *Oracle Retail Advanced Inventory Planning Implementation Guide* for details on loading data.

- Interval Hierarchy
- Poisson Distribution Table

Minimum Sales Stock

The Minimum Sales Stock (MSS) for the Poisson replenishment method is calculated as the sum of Forecasted Demand and Customer Orders over the review time.

Calculation Expressions:

MSS = Minimum Sales Stock

SS = Safety Stock

CO = Customer Orders

CORT = Customer Orders over Review Time

MSQ = Maximum Sellable Quantity

SC = Shelf Capacity (user-defined parameter)

Calculations:

Calculated MSS may not exceed Maximum Sellable Quantity (MSQ). Where it does, MSS is set to MSQ.

$$MSS = \text{Min}((\sum_{BRT}^{ERT} FD + CO), MSQ)$$

When the product/store is constrained by shelf capacity (Shelf Capacity Flag is true) the calculated MSS for stores may not exceed the level required to fill the shelf to capacity and meet CORT. Where it does, MSS is set to Shelf Capacity (SC) + CORT.

$$MSS = \text{Min}(MSS, SC + CORT)$$

Safety Stock

Poisson is a statistical method that uses a Poisson distribution lookup table. The lookup function is fed the demand over the review time and the desired service level as parameters. The Poisson table is loaded from an external source.

Calculation Expressions:

SS = Safety Stock

SL = Store Service Level (user-defined parameter)

FDRT = Forecasted Demand over Review Time

SSS = Statistical Safety Stock

SSMIN = Safety Stock Minimum

SSMAX = Safety Stock Maximum

SSLF = Safety Stock Lift Factor (user-defined parameter)

SCSSU = Supplier Compliance Safety Stock Uplift

BRT = Beginning of Review Time

ERT = End of Review Time

Calculations:

$$SSS = \text{LookupFunction}(FDRT, SL)$$

The result is then checked to ensure that it falls between the SSMIN and SSMAX boundaries determined in the safety stock range section. Finally, the safety stock level factor (SSLF) is added and the result is checked to ensure that it does not drop below zero.

$$SS = \text{Max}(\text{Max}(\text{Min}(SSS, SS\text{MAX}), SS\text{MIN}) + SSLF, 0)$$

Finally, Supplier Compliance Safety Stock Uplift is added to the calculated safety stock.

$$SS = SS + SCSSU$$

Receipt Point

Receipt Point in the Poisson method is calculated as the sum of forecasted demand over the review time plus Boundary Stock (BS).

Calculation Expressions:

RP = Receipt Point

PRP = Preliminary Receipt Point

BS = Boundary Stock

FDRT = Forecasted Demand over Review Time

CORT = Customer Orders over Review Time

DS = Demo Stock (user-defined parameter)

MSQ = Maximum Sellable Quantity

SC = Shelf Capacity (user-defined parameter)

Calculations:

$$PRP = FDRT + BS$$

Add CORT and Demo Stock and check the value does not exceed MSQ, constraining by shelf capacity when relevant.

When Shelf Capacity is not relevant for the SKU

$$RP = \text{Min}(PRP + CORT + DS, MSQ + DS)$$

When Shelf Capacity is relevant for the SKU

$$RP = \text{Min}(\text{Min}(PRP + CORT + DS, MSQ + DS), SC + CORT + DS)$$

Receive Up To Level

For Receive Up To Level (RUTL) using the Poisson replenishment method, demand is assessed over a number of days. This number of days is the larger of either the number of days in the review time, or the user-specified inventory selling days (ISD).

The RUTL is then calculated as the sum of demand over the calculated number of days commencing with the beginning of the review time. Boundary stock (BS) and safety stock level factor (SSLF) are then added.

Next, Customer Orders (CORT) and Demo Stock (DS) must be added to the previously-calculated RUTL. However, the value may not exceed the sum of MSQ plus Demo Stock.

Finally, when the product/store is constrained by shelf capacity (Shelf Capacity Flag is true), the current RUTL value is compared to the sum of Shelf Capacity (SC), CORT and Demo Stock. RUTL is set to the lesser of the two.

Calculation Expressions:*RUTL = Receive Up To Level**PRUTL = Preliminary Receive Up To Level**ND = Number of Days**ISD = Inventory Selling Days (user-defined parameter)**FD = Forecasted Demand**SSLF = Safety Stock Lift Factor (user-defined parameter)**BS = Boundary Stock**CORT = Customer Orders over Review Time**DS = Demo Stock (user-defined parameter)**MSQ = Maximum Sellable Quantity**SC = Shelf Capacity (user-defined parameter)**BRT = Beginning of Review Time**ERT = End of Review Time*Calculations:

$$ND = \text{Max}(ERT - BRT + 1, ISD)$$

$$PRUTL = \sum_{BRT}^{BRT + ND - 1} FD + BS$$

Add CORT and Demo Stock and check the value does not exceed MSQ, constraining by shelf capacity when relevant.

When Shelf Capacity is not relevant for the SKU

$$RUTL = \text{Min}(PRUTL + CORT + DS, MSQ + DS)$$

When Shelf Capacity is relevant for the SKU

$$RUTL = \text{Min}(\text{Min}(PRUTL + CORT + DS, MSQ + DS), SC + CORT + DS)$$

Maximum Sellable Quantity

For the Poisson replenishment method, Maximum Sellable Quantity (MSQ) is calculated is calculated as the sum of forecasted demand over the product life starting from the beginning of the review time and Customer Orders over Review Time.

MSQ is dependent upon Product Life (PL) and the MSQ Constraint Indicator. Where Product Life is deemed to be not relevant for a SKU and/or the MSQ Constraint Indicator is 'FALSE', the MSQ is considered infinite (Unbounded).

Calculation Expressions:*MSQ = Maximum Sellable Quantity**FD = Forecasted Demand**CORT = Customer Orders over Review Time**PL = Product Life**BRT = Beginning of Review Time*

Calculations:

When product life is not relevant for the SKU and/or the MSQ Constraint Indicator = False

$$MSQ = \text{unbounded}$$

When product life is relevant for the SKU and the MSQ Constraint Indicator = True

$$MSQ = \sum_{BRT}^{\text{Current ATP day} + (PL - 1)} FD + CORT$$

Loaded SS Dynamic Replenishment Method

The Loaded SS Dynamic replenishment method allows the user to provide a custom safety stock quantity from an external system.

Required Data

The following data must be loaded in order to use the Loaded SS Dynamic replenishment method. Please refer to the *Oracle Retail Advanced Inventory Planning Implementation Guide* for details on loading data.

- Store Loaded Safety Stock

Minimum Sales Stock

The Minimum Sales Stock (MSS) for the Loaded SS Dynamic replenishment method is calculated as the sum of Forecasted Demand and Customer Orders over the review time.

Calculation Expressions:

MSS = Minimum Sales Stock

SS = Safety Stock

CO = Customer Orders

CORT = Customer Orders over Review Time

MSQ = Maximum Sellable Quantity

SC = Shelf Capacity (user-defined parameter)

Calculations:

Calculated MSS may not exceed Maximum Sellable Quantity (MSQ). Where it does, MSS is set to MSQ.

$$MSS = \text{Min}((\sum_{BRT}^{ERT} FD + CO), MSQ)$$

When the product/store is constrained by shelf capacity (Shelf Capacity Flag is true) the calculated MSS for stores may not exceed the level required to fill the shelf to capacity and meet CORT. Where it does, MSS is set to Shelf Capacity (SC) + CORT.

$$MSS = \text{Min}(MSS, SC + CORT)$$

Safety Stock

Safety Stock in the Loaded SS Dynamic method does not calculate a Safety Stock but instead loads it from an external system. As a result, no attempt is made to confine the loaded value to the safety stock minimum and maximum limits. Supplier Compliance Safety Stock Uplift is added to the loaded safety stock.

Calculation Expressions:

$$SS = SS + SCSSU$$

SS = *Safety Stock*

$LoadedSS$ = *Loaded Safety Stock (loaded from external system)*

$SCSSU$ = *Supplier Compliance Safety Stock Uplift*

Calculation:

$$SS = LoadedSS + SCSSU$$

Receipt Point

Receipt Point in the Loaded SS Dynamic method is calculated as the sum of forecasted demand over the review time plus Boundary Stock (BS).

Calculation Expressions:

RP = *Receipt Point*

PRP = *Preliminary Receipt Point*

BS = *Boundary Stock*

$FDRT$ = *Forecasted Demand over Review Time*

$CORT$ = *Customer Orders over Review Time*

DS = *Demo Stock (user-defined parameter)*

MSQ = *Maximum Sellable Quantity*

SC = *Shelf Capacity (user-defined parameter)*

Calculations:

$$PRP = FDRT + BS$$

Add CORT and Demo Stock and check the value does not exceed MSQ, constraining by shelf capacity when relevant.

When Shelf Capacity is not relevant for the SKU:

$$RP = \text{Min}(PRP + CORT + DS, MSQ + DS)$$

When Shelf Capacity is relevant for the SKU:

$$RP = \text{Min}(\text{Min}(PRP + CORT + DS, MSQ + DS), SC + CORT + DS)$$

Receive Up To Level

For Receive Up To Level (RUTL) using the Loaded SS Dynamic replenishment method, demand is assessed over a number of days. This number of days is the larger of either the number of days in the review time, or the user-specified inventory selling days (ISD).

The RUTL is then calculated as the sum of demand over the calculated number of days commencing with the beginning of the review time. Boundary stock (BS) and safety stock level factor (SSLF) are then added.

Next, Customer Orders (CORT) and Demo Stock (DS) must be added to the previously-calculated RUTL. However, the value may not exceed the sum of MSQ plus Demo Stock.

Finally, when the product/store is constrained by shelf capacity (Shelf Capacity Flag is true), the current RUTL value is compared to the sum of Shelf Capacity (SC), CORT and Demo Stock. RUTL is set to the lesser of the two.

Calculation Expressions:

RUTL = Receive Up To Level

PRUTL = Preliminary Receive Up To Level

ND = Number of Days

ISD = Inventory Selling Days (user-defined parameter)

FD = Forecasted Demand

SSLF = Safety Stock Lift Factor (user-defined parameter)

BS = Boundary Stock

CORT = Customer Orders over Review Time

DS = Demo Stock (user-defined parameter)

MSQ = Maximum Sellable Quantity

SC = Shelf Capacity (user-defined parameter)

BRT = Beginning of Review Time

ERT = End of Review Time

Calculations:

$$ND = \text{Max}(ERT - BRT + 1, ISD)$$

$$PRUTL = \sum_{BRT}^{BRT + ND - 1} FD + BS$$

Add CORT and Demo Stock and check the value does not exceed MSQ, constraining by shelf capacity when relevant.

When Shelf Capacity is not relevant for the SKU

$$RUTL = \text{Min}(PRUTL + CORT + DS, MSQ + DS)$$

When Shelf Capacity is relevant for the SKU

$$RUTL = \text{Min}(\text{Min}(PRUTL + CORT + DS, MSQ + DS), SC + CORT + DS)$$

Maximum Sellable Quantity

For the Poisson replenishment method, Maximum Sellable Quantity (MSQ) is calculated as the sum of forecasted demand over the product life starting from the beginning of the review time and Customer Orders over Review Time.

MSQ is dependent upon Product Life (PL) and the MSQ Constraint Indicator. Where Product Life is deemed to be not relevant for a SKU and/or the MSQ Constraint Indicator is 'FALSE', the MSQ is considered infinite (Unbounded).

Calculation Expressions:

MSQ = Maximum Sellable Quantity

FD = Forecasted Demand

CORT = Customer Orders over Review Time

PL = Product Life

BRT = Beginning of Review Time

Calculations:

When product life is not relevant for the SKU and/or the MSQ Constraint Indicator = False

$$MSQ = \text{unbounded}$$

When product life is relevant for the SKU and the MSQ Constraint Indicator = True

$$MSQ = \sum_{BRT}^{\text{Current ATP day} + (PL - 1)} FD + CORT$$

Sales Week Range Replenishment Method

The Sales Week Range replenishment method allows the user to define the Safety Stock (SS), Receipt Point (RP) and Receive Up To Level (RUTL) based on sales history. The basic calculation generates Safety Stock based on the sum of sales over a user defined period in history.

Minimum Sales Stock

The Minimum Sales Stock (MSS) for the Sales Week Range replenishment method is calculated as the sum of Safety Stock and Customer Orders over the review time.

Calculation Expressions:

MSS = Minimum Sales Stock

SS = Safety Stock

CORT = Customer Orders over Review Time

MSQ = Maximum Sellable Quantity

SC = Shelf Capacity (user-defined parameter)

Calculations:

Calculated MSS may not exceed Maximum Sellable Quantity (MSQ). Where it does, MSS is set to MSQ.

$$MSS = \text{Min}(SS + CORT, MSQ)$$

When the product/store is constrained by shelf capacity (Shelf Capacity Flag is true) the calculated MSS for stores may not exceed the level required to fill the shelf to capacity and meet CORT. Where it does, MSS is set to Shelf Capacity (SC) + CORT.

$$MSS = \text{Min}(MSS, SC + CORT)$$

Safety Stock

Safety Stock for the Sales Week Range replenishment method is calculated as the total sales in a historical period specified by the user. The historical period is defined by a start and end date specified by the user.

There are two options for the Sales Week Range method controlled by the Roll Weeks Flag.

- If the Roll Weeks Flag is set to false, the historical period used in the summation of sales is static, where the sales are summed over the date range specified for each day the safety stock is calculated.
- If the Roll Weeks Flag is set to true, the historical sales period moves forward a week for each new week encountered in the planning horizon. The sales period will not roll forward beyond first day in the planning horizon.

The Roll Weeks Flag is time-phased, and so the value used through the entire planning horizon for the current run of Replenishment is the value valid for today (the current day).

The safety stock is calculated as the sum of historic sales between the current Start and End dates. The result is then checked to ensure that it falls between the optional Store Sales Min (SLSMIN) and Store Sales Max (SLSMAX) specified by the user.

Calculation Expressions:

SS = Safety Stock

SSDR = Sum of Sales over Date Range

HDS = Historical Daily Sales

SLSMIN = Store Sales Min (user-defined parameter)

SLSMAX = Store Sales Max (user-defined parameter)

SD = Start Date (user-defined parameter)

ED = End Date (user-defined parameter)

Calculations:

$$SSDR = \sum_{SD}^{ED} HDS$$

$$SS = \text{Max}(\text{Max}(\text{Min}(SLSMAX, SSDR), SLSMIN), 0)$$

Finally, Supplier Compliance Safety Stock Uplift is added to the calculated safety stock.

$$SS = SS + SCSSU$$

Note that if the 'Store Use Like SKU' is set to 'True', the historical daily sales of an alternative 'Like SKU' may be used in lieu of the sales of the SKU being replenished. If the use of a 'Like SKU' is permitted and has been specified, then its historical sales will be used if the 'Store Like SKU End Date' is greater than the first day in the planning horizon'.

Receipt Point

Receipt Point in the Sales Week Range method is set to the calculated Boundary Stock (BS).

Calculation Expressions:

RP = Receipt Point

BS = Boundary Stock

CORT = Customer Orders over Review Time

DS = Demo Stock (user-defined parameter)

MSQ = Maximum Sellable Quantity

SC = Shelf Capacity (user-defined parameter)

Calculations:

$$RP = BS$$

Add CORT and Demo Stock and check the value does not exceed MSQ, constraining by shelf capacity when relevant.

When Shelf Capacity is not relevant for the SKU

$$RP = \text{Min}(BS + CORT + DS, MSQ + DS)$$

When Shelf Capacity is relevant for the SKU

$$RP = \text{Min}(\text{Min}(BS + CORT + DS, MSQ + DS), SC + CORT + DS)$$

Receive Up To Level

Receive Up To Level in the Sales Week Range method is set to the calculated Boundary Stock (BS).

Calculation Expressions:

RUTL = Receive Up To Level

BS = Boundary Stock

CORT = Customer Orders over Review Time

DS = Demo Stock (user-defined parameter)

MSQ = Maximum Sellable Quantity

SC = Shelf Capacity (user-defined parameter)

Calculations:

$$RUTL = BS$$

Add CORT and Demo Stock and check the value does not exceed MSQ, constraining by shelf capacity when relevant.

When Shelf Capacity is not relevant for the SKU

$$RUTL = \text{Min}(BS + CORT + DS, MSQ + DS)$$

When Shelf Capacity is relevant for the SKU

$$RUTL = \text{Min}(\text{Min}(BS + CORT + DS, MSQ + DS), SC + CORT + DS)$$

Maximum Sellable Quantity

For the Sales Week Range replenishment method, Maximum Sellable Quantity (MSQ) is calculated as the sum of forecasted demand over the product life starting from the beginning of the review time and Customer Orders over Review Time.

MSQ is dependent upon Product Life (PL) and the MSQ Constraint Indicator. Where Product Life is deemed to be not relevant for a SKU and/or the MSQ Constraint Indicator is 'FALSE', the MSQ is considered infinite (Unbounded).

Calculation Expressions:

MSQ = Maximum Sellable Quantity

FD = Forecasted Demand

CORT = Customer Orders over Review Time

PL = Product Life

BRT = Beginning of Review Time

Calculations:

When product life is not relevant for the SKU and/or the MSQ Constraint Indicator = False

$$MSQ = \text{unbounded}$$

When product life is relevant for the SKU and the MSQ Constraint Indicator = True

$$MSQ = \sum_{BRT}^{\text{Current ATP day} + (PL - 1)} FD + CORT$$

Factor AWS Replenishment Method

The Factor AWS replenishment method allows the user to define the Safety Stock (SS), Receipt Point (RP) and Receive Up To Level (RUTL) based on average weekly sales. Sales are averaged over a user designated time period to arrive at an Average Weekly Sales (AWS) value. The AWS is multiplied by a user designated factor to generate Safety Stock.

Minimum Sales Stock

The Minimum Sales Stock (MSS) for the Factor AWS replenishment method is calculated as the sum of Safety Stock and Customer Orders over the review time.

Calculation Expressions:

MSS = Minimum Sales Stock

SS = Safety Stock

CORT = Customer Orders over Review Time

MSQ = Maximum Sellable Quantity

SC = Shelf Capacity (user-defined parameter)

Calculations:

Calculated MSS may not exceed Maximum Sellable Quantity (MSQ). Where it does, MSS is set to MSQ.

$$MSS = \text{Min}(SS + CORT, MSQ)$$

When the product/store is constrained by shelf capacity (Shelf Capacity Flag is true) the calculated MSS for stores may not exceed the level required to fill the shelf to capacity and meet CORT. Where it does, MSS is set to Shelf Capacity (SC) + CORT.

$$MSS = \text{Min}(MSS, SC + CORT)$$

Safety Stock

Safety Stock for the Factor AWS replenishment method calculates Average Weekly Sales (AWS) and multiplies it by a user specified factor. AWS is calculated using sales in a historical period specified by the user. The historical period is defined by a start and end date specified by the user.

There are two options for the Sales Week Range method controlled by the Roll Weeks Flag.

- If the Roll Weeks Flag is set to false, the historical period used in the AWS calculation is static, where the AWS is calculated using the date range specified for each day the safety stock is calculated.
- If the Roll Weeks Flag is set to true, the historical sales period moves forward a week for each new week encountered in the planning horizon. The sales period will not roll forward beyond first day in the planning horizon.

The Roll Weeks Flag is time-phased, and so the value used through the entire planning horizon for the current run of Replenishment is the value valid for today (the current day).

The safety stock is calculated as the sum of historic sales between the current Start and End dates. The result is then checked to ensure that it falls between the optional Store Sales Min (SLSMIN) and Store Sales Max (SLSMAX) specified by the user.

The safety stock is calculated as the average of the historic daily sales between the current Start and End dates. This number is then multiplied by 7 to achieve a weekly value. The weekly value is then multiplied by a user specified Average Weekly Sale Factor. The result is then checked to ensure that it falls between the optional Store Sales Min (SLSMIN) and Store Sales Max (SLSMAX) specified by the user.

First, calculate the number of days in the historical date range.

$$NDR = ED - SD + 1$$

Sum the historical daily sales over the date range.

$$SSDR = \sum_{SD}^{ED} HDS$$

Divide the sum of historical daily by the number of days in the historical date range to get the daily average and multiply by 7 to get the weekly average.

$$AWS = \left(\frac{SSDR}{NDR} \right) * 7$$

Apply the Store Sales Min and Max boundaries.

$$SS = \text{Max}(\text{Max}(\text{Min}(SLSMAX, SSDR), SLSMIN), 0)$$

Finally, Supplier Compliance Safety Stock Uplift is added to the calculated safety stock.

$$SS = SS + SCSSU$$

Note that if the 'Store Use Like SKU' is set to 'True', the historical daily sales of an alternative 'Like SKU' may be used in lieu of the sales of the SKU being replenished. If the use of a 'Like SKU' is permitted and has been specified, then its historical sales will be used if the 'Store Like SKU End Date' is greater than the first day in the planning horizon'.

Receipt Point

Receipt Point in the Factor AWS method is set to the calculated Boundary Stock (BS).

Calculation Expressions:

RP = Receipt Point

BS = Boundary Stock

CORT = Customer Orders over Review Time

DS = Demo Stock (user-defined parameter)

MSQ = Maximum Sellable Quantity

SC = Shelf Capacity (user-defined parameter)

Calculations:

$$RP = BS$$

Add CORT and Demo Stock and check the value does not exceed MSQ, constraining by shelf capacity when relevant.

When Shelf Capacity is not relevant for the SKU:

$$RP = \text{Min}(BS + CORT + DS, MSQ + DS)$$

When Shelf Capacity is relevant for the SKU:

$$RP = \text{Min}(\text{Min}(BS + CORT + DS, MSQ + DS), SC + CORT + DS)$$

Receive Up To Level

Receive Up To Level in the Factor AWS method is set to the calculated Boundary Stock (BS).

Calculation Expressions:

RUTL = Receive Up To Level

BS = Boundary Stock

CORT = Customer Orders over Review Time

DS = Demo Stock (user-defined parameter)

MSQ = Maximum Sellable Quantity

SC = Shelf Capacity (user-defined parameter)

Calculations:

$$RUTL = BS$$

Add CORT and Demo Stock and check the value does not exceed MSQ, constraining by shelf capacity when relevant.

When Shelf Capacity is not relevant for the SKU:

$$RUTL = \text{Min}(BS + CORT + DS, MSQ + DS)$$

When Shelf Capacity is relevant for the SKU:

$$RUTL = \text{Min}(\text{Min}(BS + CORT + DS, MSQ + DS), SC + CORT + DS)$$

Maximum Sellable Quantity

For the Factor AWS replenishment method, Maximum Sellable Quantity (MSQ) is calculated as the sum of forecasted demand over the product life starting from the beginning of the review time and Customer Orders over Review Time.

MSQ is dependent upon Product Life (PL) and the MSQ Constraint Indicator. Where Product Life is deemed to be not relevant for a SKU and/or the MSQ Constraint Indicator is 'FALSE', the MSQ is considered infinite (Unbounded).

Calculation Expressions:

MSQ = Maximum Sellable Quantity

FD = Forecasted Demand

CORT = Customer Orders over Review Time

PL = Product Life

BRT = Beginning of Review Time

Calculations:

When product life is not relevant for the SKU and/or the MSQ Constraint Indicator = False

$$MSQ = \text{unbounded}$$

When product life is relevant for the SKU and the MSQ Constraint Indicator = True

$$MSQ = \sum_{BRT}^{Current\ ATP\ day\ (PL-1)} FD + CORT$$

Calculate an Unconstrained Receipt Plan

Current Inventory and Projected Inventory

Projected Inventory (PI) represents a projection of the opening inventory position for any day in the planning horizon at a specific destination. None of that day's activities (either receipts or demand) are reflected in PI, and so it is often referred to as a "beginning of day" position.

Projected Inventory for today is equal to the on hand inventory at the store - Current Store Inventory (CSI).

Calculation Expressions:

PI = Projected Inventory

CSI = Current Store Inventory

Calculation:

$$PI_{today} = CSI$$

Projected Inventory on day t is calculated as the PI of the previous day (t-1) plus the net impact of all demand, supply and spoilage on the previous day. Demand on the previous day is considered to be Forecasted Demand (FD) plus any Customer Orders (CO) on that day. Supply on the previous day is considered to be Expected and Planned Receipts (ER & PR). Spoilage is the calculated Expected Spoilage (ES) for the previous day.

In summary, PI for day t, where t is not today, is calculated as follows:

Calculation Expressions:

PI = Projected Inventory

ER = Expected Receipts

ES = Expected Spoilage

FD = Forecasted Demand

PR = Planned Receipts

CO = Customer Orders

Calculation:

$$PI_t = \text{Max}(PI_{t-1} - ER_{t-1} - FD_{t-1} - ES_{t-1} + PR_{t-1} + CO_{t-1}, 0)$$

Planned Receipts (PR) are assumed to be unconstrained during replenishment and constrained during reconciliation.

Where a Current Inventory Feed is not available for today, then a contingency Projected Inventory calculation is used.

The contingency PI is calculated as yesterday's calculated PI for today plus the difference between forecast demand (sales) for yesterday and Actual Sales for yesterday. If actual sales are not available for yesterday, then PI for today should simply be set to yesterday's projection of PI for today.

Calculation Expressions:

CPI = Contingency Projected Inventory

YPI = Yesterday's Calculated Projected Inventory

PI = Projected Inventory

FD = Forecasted Demand

ActSls = Actual Sales

Calculations:

If yesterday's actual sales also available, then:

$$CPI_{today} = YPI_t + (FD_{t-1} - ActSls_{t-1})$$

If yesterday's actual sales also not available, then:

$$CPI_{today} = YPI_t$$

Note: Yesterday's Calculated Projected Inventory is the Projected Inventory for today as it was calculated yesterday. For example, on Monday we calculate a PI for Tuesday. If on Tuesday, no current inventory is available, the contingency PI is calculated using Tuesday's PI that was calculated on Monday. The difference between the forecast and actual sales from Monday is then added. The result is used as the beginning inventory position for Tuesday.

Net Inventory

Net Inventory (NI) is a prediction of the inventory position at the end of a specific period of time. It does not consider demand over the specified period, and so it often referred as Available Inventory – as it ultimately represents what inventory will be available to meet demand over the period.

All NI calculations are based upon a Projected Inventory position at the beginning of the period and then consider the impact of expected receipts and expected spoilage (ER & ES) over the review time.

Expected Spoilage is calculated as an end of day quantity. Therefore, the Spoilage calculated for the last day of the review period has no impact on any ability to meet demand in the review period. Therefore, the period over which spoilage should be considered must be shortened by one day. Therefore the spoilage period commences on the BRT and finishes on (but includes) the ERT minus one day.

In summary, for Replenishment, the definition of NI associated with a given ATP day is shown below.

Calculation Expressions:

NI = Net Inventory

PI = Projected Inventory

ER = Expected Receipts

ES = Expected Spoilage

BRT = Beginning of Review Time

ERT = End of Review Time

ATP = Available to Plan Day

Calculation:

$$NI_{ATP} = \text{Max}\left(PI_{BRT_{ATP}} + \left(\sum_{BRT_{ATP}}^{ERT_{ATP}} ER\right) - \left(\sum_{BRT_{ATP}}^{ERT_{ATP}-1} ES\right), 0\right)$$

Calculate Ideal Receipt Quantity

The Ideal Receipt Quantity (IRQ) calculation is the process of actually determining what the order quantity should be. This is the same process for all methods except No Replenishment. For No Replenishment, the IRQ is assumed to be zero.

The determination of IRQ is impacted by the presence of User Specified Allocations (USA). If the ATP day being planned is before the On Supply Date for the SKU/Store or is after the Off Supply Date but within 42 days after it, then the IRQ should be set as the total of all USAs within the review time for the ATP day.

Calculation Expressions:

IRQ = Ideal Receipt Quantity

USA = User Specified Allocation

BRT = Beginning of Review Time

ERT = End of Review Time

ATP = Available to Plan Day

Calculations:

If $t > ((\text{OnSupply} - 35) \text{ AND } t < (\text{OnSupply}))$

OR

$((t > \text{OffSupply} \text{ AND } t < \text{OffSupply} + 42))$

$$IRQ_t = \sum_{BRT}^{ERT} USA$$

where t is the ATP day being planned.

When the ATP day being planned falls within the On and Off Supply dates, the Net Inventory (NI) is compared to the Receipt Point (RP). If the Net Inventory is less than the Receipt Point, then the initial IRQ is calculated as the Receive Up To Level (RUTL) minus the Net Inventory.

Calculation Expressions:*IRQ* = Ideal Receipt Quantity*RUTL* = Receive Up To Level*NI* = Net Inventory*ATP* = Available to Plan DayCalculation:

$$IRQ_{ATP} = RUTL_{ATP} - NI_{ATP}$$

If there are USAs in the review time of the ATP being planned, then the IRQ is further modified. This modification depends upon the type of the first USA encountered in the review time. If the type is replace, then the sum of all the USAs in the review time replaces the calculated IRQ. If the type is "Add", then the sum of all the USAs in the review time is added to the calculated IRQ.

Calculation Expressions:*IRQ* = Ideal Receipt Quantity*USA* = User Specified Allocation*BRT* = Beginning of Review Time*ERT* = End of Review Time*ATP* = Available to Plan DayCalculations:

If there are USAs in the Review Time:

Determine USA Type (type of USA first encountered in Review Time)

If USA type = Replace

$$IRQ_t = \sum_{BRT}^{ERT} USA$$

If USA type = Add

$$IRQ_t = IRQ_t + \sum_{BRT}^{ERT} USA$$

where t is the ATP day being planned

Finally, the IRQ is checked against Customer Orders over Review Time (CORT). If Product Life is relevant for the SKU and the Freshness Flag is true, then the IRQ must be no less than CORT. If IRQ is less than CORT, the IRQ is set to CORT. This guarantees the freshest product is available to meet CORT.

If product life is not relevant for the SKU or the freshness flag is not true, then the inventory position including IRQ (*NI* + *IRQ*) must be no less than CORT. If it is, then the IRQ is set as (CORT – *NI*). This ensures there will be sufficient inventory once the order has been received to meet CORT.

Calculation Expressions:*IRQ* = Ideal Receipt Quantity*CORT* = Receive Up To Level*NI* = Net Inventory

Calculation:

When product life is relevant for the SKU:

$$IRQ_t = \text{Max}(IRQ_t, CORT)$$

where t is the ATP day being planned.

When product life is not relevant for the SKU:

$$IRQ_t = \text{Max}(NI + IRQ_t, CORT) - NI$$

where t is the ATP day being planned.

Round Ideal Receipt Quantity

Round to Pack Size

The calculated ideal receipt quantity is in units. The order quantities to the source are in order multiple quantities. The IRQ is converted to a multiple of the Store Ordering Pack Size.

Calculation Expressions:

PFP = Portion of the Final Pack

PSZ = Pack Size

IRQ = Ideal Receipt Quantity

RNP = Raw Number of Packs

Calculations:

First, the raw number of packs to be received is calculated:

$$RNP_t = \frac{IRQ_t}{PSZ_t}$$

where t is the ATP day being planned.

The IRQ Remainder is the fraction of a pack resulting from the RNP calculation.

$$IRQ_{\text{Remainder}} = RNP_t - \text{Floor}(RNP_t)$$

where t is the ATP day being planned.

For example, if

$$IRQ = 40$$

$$PSZ = 12$$

Then,

$$RNP = 40/12 = 3.33$$

And

$$IRQ_{\text{Remainder}} = 3.33 - 3 = .33$$

Note that Floor(x) indicates 'x' is rounded down and Ceil (x) indicates 'x' is rounded up.

If there is a remaining IRQ greater than zero, a decision must be made whether to order an additional whole order multiple or to do nothing (effectively rounding down).

Effect of Order Pack and Normal Rounding Rules

When the total IRQ is less than one pack size, Order Pack and Normal rounding rules are used to determine the order quantity. The decision of whether to order a pack size is based upon the user-specified rounding method.

User Specified Rounding Method	Action Taken
Normal	Use Normal rounding rules.
Order Pack	Add pack size if NI < SS.

If the instruction is “Use normal rounding rules”, rounding will be done according to the rules described on the sections below.

If the resulting action is “Add pack size if NI < SS”, the IRQ is equal to one pack size if the Net Inventory (NI) position is less than the safety stock (SS). No further rounding is needed. If the NI is not less than the SS, rounding will be done according to the rules described on the sections below.

Effect of Freshness Flag on Rounding

The user-specified Freshness Flag is used to determine whether or not a store receipt alone must cover all customer orders over the review time.

Freshness Flag is True

Setting the Freshness Flag to true ensures that a store receipt is generated for at least the customer orders over the review time (CORT) regardless of the net inventory. In other words, the IRQ alone must be able to meet CORT. This ensures that the CORT will be met by the freshest possible inventory.

Calculation Expressions:

CORT = Customer Orders over Review Time

IRQ = Ideal Receipt Quantity

PSZ = Pack Size

RNP = Raw Number of Packs

Calculations:

If IRQ is less than or equal to CORT rounded up, the IRQ will be equal to the CORT rounded up.

$$IRQ_t = Ceil\left(\frac{CORT_t}{PSZ_t}\right) * PSZ_t$$

where t is the ATP day being planned.

If IRQ is greater than CORT rounded up, check to see if the IRQ needs to be rounded up or down to meet CORT.

If IRQ rounded down is less than CORT, IRQ will equal IRQ rounded up.

$$IF CORT_t \geq Floor(RNP_t * PSZ_t)$$

$$IRQ_t = Ceil(RNP_t * PSZ_t)$$

where t is the ATP day being planned.

Otherwise, MSQ and Acceptable Loss Limit are checked. Reference the 'Effect of Maximum Selling Quantity on Rounding' section below for details.

Freshness Flag is False

If the freshness indicator is not on, the store's inventory is taken into account. If pack rounding the IRQ down will not cover the customer orders over the review time, the IRQ is pack rounded up.

Calculation Expressions:

NI = Net Inventory

RNP = Raw Number of Packs

PSZ = Pack Size

CORT = Customer Orders over Review Time

IRQ = Ideal Receipt Quantity

Calculations:

$$IF NI_t + (Floor(RNP_t * PSZ_t)) < CORT_t$$

$$IRQ_t = Ceil(RNP_t * PSZ_t)$$

where t is the ATP day being planned

Otherwise, MSQ and Acceptable Loss Limit are checked. Reference the 'Effect of Maximum Selling Quantity on Rounding' section below for details.

Effect of Maximum Selling Quantity on Rounding

Maximum Sellable Quantity is the amount of stock that can be sold within the life of perishable product based on demand forecast.

SAL represents the percentage of a pack size the user is prepared to lose in order to meet sales.

Once AIP has ensured that all customer orders over the review time will be met, AIP checks whether rounding up to a pack will cause the inventory to be greater than the maximum sellable quantity. If so, AIP verifies that rounding up is within the spoilage threshold.

Calculation Expressions:*NI = Net Inventory**IRQ = Ideal Receipt Quantity**PSZ = Pack Size**MSQ = Maximum Sellable Quantity**SAL = Acceptable Loss Percentage*Calculation Expressions:

If the total inventory for the SKU at the store after rounding up does not exceed the Maximum Sellable Quantity (MSQ), the IRQ is rounded up. Total inventory is calculated as the NI position plus the IRQ plus another pack size.

$$\text{If } \left(\frac{(NI + IRQ_t + PSZ_t)}{PSZ_t} \right) \leq MSQ$$

$$IRQ_t = \text{Ceil} \left(\frac{IRQ_t}{PSZ_t} * PSZ_t \right)$$

where t is the ATP day being planned

If the total inventory at the store after rounding up (as calculated in the previous step) exceeds the calculated MSQ but the amount over MSQ as a proportion of a pack size does not exceed the user-specified Acceptable Loss Percentage (SAL), the IRQ is rounded up.

$$\text{If } \left(\frac{(NI + IRQ_t + PSZ_t - MSQ_t)}{PSZ_t} \right) \leq SAL$$

$$IRQ_t = \text{Ceil} \left(\frac{IRQ_t}{PSZ_t} * PSZ_t \right)$$

where t is the ATP day being planned

If neither of the above conditions is met, IRQ is rounded down.

$$IRQ_t = \text{Floor} \left(\frac{IRQ_t}{PSZ_t} * PSZ_t \right)$$

where t is the ATP day being planned.

Effect of Store Rounding Threshold on Rounding

The next step is rounding the order according to the Store Rounding threshold.

The Store Rounding Threshold (RTH) is the portion of a pack above which the receipt quantity is rounded up and below which it is rounded down.

If the IRQ Remainder is greater than or equal to the rounding threshold, the ideal receipt quantity rounded is rounded up. Otherwise, it is rounded down.

Calculation Expressions:*IRQ = Ideal Receipt Quantity**PSZ = Pack Size*

If IRQ Remainder is greater than or equal to the rounding threshold,

$$IRQ_t = Ceil\left(\frac{IRQ_t}{PSZ_t} * PSZ_t\right)$$

where t is the ATP day being planned.

If IRQ Remainder is less than the rounding threshold,

$$IRQ_t = Floor\left(\frac{IRQ_t}{PSZ_t} * PSZ_t\right)$$

where t is the ATP day being planned.

Pallet Rounding

The IRQ is now rounded to pallets. Pallet rounding only occurs if Cases per Pallet (CPP) is greater than zero. Cases per Pallet are converted to Units per Pallet (UPP) by multiplying the CPP value by the pack size.

Next the IRQ is calculated as a proportion a pallet. If the proportion a pallet is greater than or equal to a user-defined Percent of Pallet (POP) threshold, the IRQ is rounded up to the next whole pallet number if either one of two further conditions are met:

- If product life is not relevant for the SKU.
- If rounding the order up to the next whole pallet means that the subsequent inventory position in the store does not exceed the MSQ.

Calculate Units per Pallet

Calculation Expressions:

CPP = Cases per Pallet

PSZ = Pack Size

UPP = Units per Pallet

Calculation:

*UPP = CPP * PSZ*

Calculate IRQ as a portion of a pallet

$$IPP = \frac{IRQ_t}{UPP}$$

where t is the ATP day being planned.

If (POP > 0) AND (IPP - Floor(IPP)) ≥ POP

If product life is not relevant for the SKU

OR

*NI_t + Ceil(IPP) * UPP ≤ MSQ_t*

Then

$$IRQ_t = Ceil(IPP) * UPP$$

where t is the ATP day being planned.

Inventory Capping

When store space is at a premium, SKU Caps can be set to limit the IRQ.

Space (capping) constraints are applied to the Store IRQ for any SKU for which the Capping Flag is set to TRUE.

The Store IRQ for a SKU on a given ATP day is calculated and capped by the Available Space on the ATP day.

First, the Rounded Store Available Space (RSAS) is calculated:

Calculation Expressions:

SAS = Store Available Space

RSAS = Rounded Store Available Space

OM = Order Multiple

Calculations:

$$RSAS_t = RoundDown(SAS_t, OM_t)$$

where t is the ATP day being planned.

Next, the IRQ capped by the Rounded Available Space (RSAS) is calculated:

Calculation Expressions:

IRQ = Ideal Receipt Quantity

RSAS = Rounded Store Available Space

Calculations:

$$IRQ_t = Min(IRQ_t, RSAS_t)$$

where t is the ATP day being planned.

Reconciliation

In the replenishment process, a receipt plan was generated for all stores to satisfy their future inventory needs. The replenishment receipt plan is unconstrained; it assumes the inventory at the source is unlimited. In reality, the inventory at the source is limited and may not meet the demand from the store. If the available inventory at a source is insufficient to meet the needs of all stores being supplied from that source, the shortfall reconciliation algorithm is run to distribute the limited inventory.

Reconciliation is source-centric, looking at the current inventory at the source, the aggregated demand from the stores and any other locations for that source, and expected receipts to project the available inventory position in the future. Using the available inventory reconciliation allocates shipments to stores and warehouses based on their priority and need. For capped SKUs, this available inventory is compared against the URPs, which have been generated after capping, at the stores. This ensures that the store's receipt never violates the capping constraints.

Reconciliation occurs only during the fixed period, the period of time for a location inside which the supply of inventory for a SKU-Pack is ultimately constrained – or fixed. In a multi-tier supply chain, the fixed period for a store is the time period it takes for an order to be delivered from a supplier, and pass through the appropriate levels of the supply chain to reach the store.

Two types of reconciliation are available for a SKU. Day-on-Day Reconciliation allocates inventory based on orders that can be shipped that day. Future demand to be shipped at a later date is not considered. This method ensures that any available inventory shipped that day will be in stores as early as possible.

Reconciliation over Time allocates inventory based on orders that can be shipped through the time of the next planned delivery to the source. The need over this time period (reconciliation period) is distributed across all stores. This method allows stores that would be shipped on a later date within the reconciliation period to receive a share of the available source inventory. In essence, the need for all stores for a SKU sharing the same source will be respected over the entire period for the SKU/Source.

The reconciliation period for Day-on-Day Reconciliation is one day.

Total Demand and Available Inventory

Calculate Total Demand

Total demand at the source is calculated over the reconciliation period under consideration. Total demand at a source for a given reconciliation period is the aggregate of all receipts to the destinations from the source during the same period.

Total demand at the source is calculated as the aggregated demand from all receiving locations (stores and warehouses) from the current day through the last day of the reconciliation period.

Calculation Expressions:

TotDmd = Total Demand

AggDmd = Aggregated Demand from Receiving Locations

LDRP = Last Day of the Reconciliation Period

Calculation:

$$TotDmd_t = LDRP \sum_t AggDmd$$

where t is the source ship day being planned.

For Day-on-Day Reconciliation the aggregated demand is summed over one day only.

For Reconciliation over Time the aggregated demand is summed over the review time of the source. In this case, LDRP will be the last day of review time at source.

Calculate Available Inventory at Source

The source's available inventory at source is compared against the demand from destinations to determine if there is a shortage.

Calculation Expressions:*AI = Available Inventory**PI = Projected Inventory**LDRP = Last Day of Reconciliation Period**RALT = Receiver to Availability Lead Time**ER = Expected Receipts**CRP = Constrained Receipt Plan**RecPer = Reconciliation Period**HldBk = Holdback Quantity*Calculation:

$$AI_{RecPer} = PI_t + \left(\sum_t^{LDRP-RALT} ER + CRP \right) - HldBk$$

Allocation Process

Once it is determined that reconciliation is required, the process uses a store priority matrix to determine each stores allocation.

Each store shipment was created to fulfill store need. Store need may have the following allocation boundary elements:

- Customer orders over time (CORT)
- Minimum sales stock (MSS)
- Receipt point (RP)
- Receive up to level (RUTL)
- Maximum sellable quantity (MSQ)

Note: MSQ is included above because it is an allocation boundary. The MSQ is a boundary used for stockless items; therefore it will not be included in the logic for the shortfall reconciliation.

In addition, each store will be assigned a store priority. The store priorities include:

- Super High
- High
- Normal

SRP Reconciliation Matrix Process Sequence

Store Priority	Allocation Boundary			
	CORT	MSS	RP	RUTL
Super High	1	4	5	6
High	2	7	9	11
Normal	3	8	10	12

The sequence process defines the order of priority of the combination of store priority and allocation boundary. For example, available inventory will first be used to fulfill customer orders over review time (CORT) for super high stores (number 1 above). If inventory remains, CORT for high stores is fulfilled. Next CORT for normal stores is processed, then minimum sales stock for super high stores, and so on.

Warehouses are reconciled after stores.

- The shortage priority matrix illustrates the priority order in which destinations served by a given source have to be allocated inventory in the event of a shortage.
- Stores are not allocated inventory individually – they are allocated inventory as groups. Each store is assigned to a group based on its priority. For example, all Super High stores are grouped together for processing

Determine Active Zone


The 'active zone' represents the first allocation boundary that cannot be met for all stores in a group using the sources available inventory.

This 'active zone' process is applied to all store shipments over the reconciliation period. The active zone is the cell of the priority matrix to which available inventory cannot completely fulfill. For example, if available inventory was sufficient to fill up to the minimum sales stock (MSS) for all high priority stores (zone 7) across the reconcile period, but not the MSS for normal priority stores (zone 8) across the reconciliation period, zone 8 would represent the active zone. All inventory requirements of zone 1 to zone 7 would be fulfilled with available inventory. Residual inventory would be 'watershed' across the stores in zone 8 across the reconciliation period.

Use Watershed Algorithm for Allocation

While the watershed algorithm is complex, the basic premise is to bring all stores in the priority group up to a target ratio. The Target Stock Ratio is calculated by dividing the source's total available by its total need.

One way to think of this procedure is through an analogy of water filling a container. The fill line of the container represents 100% of need for all the locations, and the quantity of water we have represents the stock available. By pouring all of our water into the container the water level naturally reaches our Target Stock Ratio. If we imagine the bottom of the container to be partitioned to represent our different stores, then the water above each partition represents each location's stock ratio as well. The water naturally levels itself to maintain a consistent stock ratio across all warehouses.



Watershed Example

In this example, our target ratio is 64%. The purple bars on the chart represent the amount of inventory available at each store. The blue bars represent available inventory from the source allocated to the stores. In this case, only 6 of the stores are allocated additional inventory.

Substitution

Once the shortfall reconciliation process is complete, shortages may still exist. The next step in calculating the store receipt plan is to check for the availability of other SKU-packs that can be substituted for the original SKU-pack.

The first step in the substitution process is to determine which SKU-packs are valid for substitution using the following criteria:

- First, the demand group of the original SKU-pack is searched. The SKU-pack with the largest pack size is selected first and all available inventory of this SKU-pack is used to satisfy shortage of original SKU-pack. After exhausting this SKU-pack, if shortage still remains then the SKU-pack with the next largest pack size is selected. This process goes on from largest to smallest until either all shortage is satisfied or all substitutes within the demand group have been exhausted.
- Once all substitutes within the demand group are exhausted, other demand groups are searched for substitutes. In this case, the original SKU must associated SKU-packs in other valid demand groups. The original demand group must have Demand Group specifier greater than the specifier of substitute demand group.

If a valid substitute has inventory available, this inventory is used to as much of the meeting at unfulfilled demand of the original SKU-pack as possible. If all the demand cannot be met using the substitute, allocation will attempt to distribute the limited substitute inventory based on allocation boundaries associated with the original SKU-pack.

Review Alerts and Manage Exceptions

SRP generates alerts as a means of indicating the user of possible problems in the supply chain, such as low stock or out of stock, overstocks, or other problems for a store.

SRP Alerts warn the user about historical and/or future problems adversely affecting a store's ability to meet sales.

Alerts are notifications that are sent to users about measures whose values are above or below an established acceptance range or threshold. Whenever values for these measures fall outside of this established range, an exception is generated, which causes alerts to be displayed in the Alert Manager window when the user logs on to SRP. This provides a means of easily viewing problem situations on an exception basis and following with the appropriate action.

Alerts are calculated in a nightly batch process. Review of alerts and the management of exceptions is an interactive process that is performed by the user during the day following the batch run.

The process of reviewing alerts and managing exceptions involves the following tasks:

- Review alerts – The Alert Manager provides notification of any exceptions generated and allows the user to transfer to the appropriate workbook(s) to research the root cause of the problem.
- Maintain parameters – Occasionally the SRP parameters used in the store replenishment planning process may need modification to produce a better plan.
- Maintain alert parameters – Alerts are triggered based on thresholds, alert horizons, and parameters. These parameters and thresholds may need tuning to control the number and types of alerts.
- Perform what-if analysis on replenishment plans – What-if analysis can be useful in comparing the current store plan with a 'what-if' plan based on parameter changes. This allows the user the flexibility of analyzing the effect of changed values on the plan without making the changes permanent.

This section provides the following information:

- Summary of SRP Alerts, followed by a more detailed description of each alert
- Using the Alert Manager
- Using SRP workbooks to analyze alerts
- Using SRP workbooks to maintain alert parameter or replenishment parameters

SRP Alerts

SRP alerts are divided into three categories:

- Historical Availability Alerts – Provide notification of historical conditions indicating various adverse conditions in a store experienced by a store, such as stock out or low inventory.
- Projected Availability Alerts – Provide notification of future conditions of forecasted conditions that could cause future stock problems for a store, such as project stock outs or low inventory, along with possible high inventory levels.

- Other Alerts – Miscellaneous alerts which provide warning information not necessarily related to stocking levels.

Historical Availability Alerts

Historical Availability Alerts provide notification of historical conditions indicating various adverse conditions in a store experienced by a store, such as stock out or low inventory.

The following table lists historical alerts issued by SRP along with a brief description. Details for each alert are addressed in the following sections.

Alert	Description
Large Consecutive Out of Stocks Over the Horizon	A Large Consecutive Out of Stocks alert is generated when a significant number of stores that have been out of stock for more than a defined number of consecutive days and the amount of lost sales is above a threshold. Only those stores that are out of stock (OOS) for the product last night will be alerted.
Large Non-Consecutive Out of Stocks	A Large Non-Consecutive Out of Stocks alert is generated when a significant number of stores that have been out of stock for more than a defined number of non-consecutive of days or the amount of lost sales is above a threshold. Only those stores that are out of stock (OOS) for the product last night will be alerted. Stores alerted for Large Consecutive Out of Stocks will not be alerted.
Large Out of Stocks Last Night	A Large Out of Stocks Last Night alert is generated when a significant number of stores are out of stock or a significant portion of possible sales yesterday are lost for a specific SKU or when the lost sales for the SKU at the company level is significant. Only those stores that are out of stock (OOS) for the product last night will be alerted. Stores alerted for Large Consecutive Out of Stocks will not be alerted.
Day on Day Repeat Out of Stocks Alert	A Day on Day Repeat Out of Stocks alert is generated when a significant number of stores have been out of stock on the same day in consecutive weeks, and the amount of lost sales is above a threshold. Only those stores that are out of stock (OOS) for the product last night will be alerted. Stores alerted for Large Consecutive Out of Stocks or Large Non-Consecutive Out of Stocks will not be alerted.

Alert	Description
Single Store Availability Problems	A Single Store Availability Problems alert is generated when a single store has been out of stock for more than a specified number of non-consecutive days, and the amount of lost sales is above a threshold. Only those stores that are out of stock (OOS) for the product last night will be alerted. Stores alerted for Large Consecutive Out of Stocks, Large Non-Consecutive Out of Stocks, Large Out of Stocks Last Night, or Day on Day Repeat Out of Stocks will not be alerted.
Historical Availability Summary Alert	A Historical Availability Summary Alert is raised when any alert in the Historic Availability Alerts Group is generated. The summary allows the user to view any store with historic out of stocks or low stocks.

Before highlighting the functionality for each of the alerts, it is important to discuss some of the key inputs to these alerts.

- Yesterday's Projected Inventory contains the amount of inventory the store started off with at the beginning of yesterday.
- Historical Demand holds the forecasted demand from yesterday for a SKU at each store.
- Lost Sales represents the number of lost sales for a SKU at a particular store. Of course, only days in the past can be accounted for in lost sales. Lost Sales is calculated as follows:
 If Yesterday's Projected Inventory is 0
 Lost Sales for yesterday = max(Historical Demand for yesterday – Daily Sales for yesterday, 0)
 Else
 Lost Sales for yesterday = 0
 Calculated Lost Sales for days prior to yesterday are retained and purged in the same manner as other historical measures.

Large Consecutive Out of Stocks Over the Horizon

A Large Consecutive Out of Stocks alert is generated when a significant number of stores that have been out of stock for more than a defined number of consecutive days and the amount of lost sales is above a threshold.

Only those stores that are out of stock (OOS) for the product last night will be alerted.

Alert Parameters

- Large OOS Horizon
- Large Cons. OOS Number of Consecutive Days OOS
- Large Cons. OOS Alerting Stores Ratio
- Large Cons. OOS Corp. Lost Sales Volume over horizon

Alert Logic Summarized

The Large Consecutive Out of Stocks alert is triggered if all of the following conditions are true:

1. Calculate the ratio of the number of stores out of stock (OOS) on a user-defined number of consecutive days over the user-defined alert horizon against the number of stores ranged for that SKU. The calculated ratio must be greater than a user-defined threshold.
 - First, the number of consecutive days a store is out of stock (days OOS) is counted, starting with and including yesterday, over the alert horizon. The alert horizon is an alert parameter, Large OOS Horizon, defining the number of days over which calculations are performed for this alert. This parameter is maintained in the SRP Alert Maintenance workbook at the SKU/Store or Sub-Class/Company level.
 - The days OOS is compared to a second alert parameter, Large Cons. OOS Number of Consecutive Days OOS. This parameter is maintained in the SRP Alert Maintenance workbook at the SKU/Store or Sub-Class/Company level. If the day OOS is greater than this parameter, the store is considered out of stock for consecutive days (OOS store).
 - To determine if the number of OOS stores is significant, a ratio (OOS ratio) is calculated as the number of OOS stores divided by the total number of stores for that SKU. The OOS stores are considered significant if the ratio is greater than an alert parameter, Large Cons. OOS Alerting Stores Ratio. This parameter is maintained in the SRP Alert Maintenance workbook at the SKU/Store or (SKU/Company) level.
 - If the OOS ratio is greater than the Large Cons. OOS Alerting Stores Ratio, the first condition for this alert is true.
2. The Total sum of lost sales over horizon from the SKU/store(s) that satisfy the consecutive OOS threshold is greater than a set volume threshold.
 - First, total the lost sales over the alert horizon (Large OOS Horizon parameter) for the OOS stores.
 - The sum of lost sales is compared to an alert parameter, Large Cons. OOS Corp. Lost Sales Volume over horizon (Large OOS volume). This parameter is maintained in the SRP Alert Maintenance workbook at the SKU/Store or (SKU/Company) level.
 - If the total lost sales for the OOS stores is greater than the Large OOS volume, this condition is true.
3. If the SKU was out of stock last night for this store, condition 3 is true.

Large Non-Consecutive Out of Stocks over the Horizon

A Large Non-Consecutive Out of Stocks alert is generated when a significant number of stores that have been out of stock for more than a defined number of non-consecutive of days and the amount of lost sales is above a threshold.

Only those stores that are out of stock (OOS) for the product last night will be alerted.

Stores alerted for Large Consecutive Out of Stocks will not be alerted.

Alert Parameters

- Large OOS Horizon
- Large Non-Cons. OOS Number of Consecutive Days OOS
- Large Non-Cons. OOS Alerting Stores Ratio
- Large Non-Cons. OOS Corp. Lost Sales Volume over horizon

Alert Logic Summarized

The Large Non-Consecutive Out of Stocks alert is triggered if all of the following conditions are true:

1. Calculate the ratio of the number of stores out of stock (OOS) on a user-defined number of non-consecutive days over the user-defined alert horizon against the number of stores ranged for that SKU. The calculated ratio must be greater than a user-defined threshold.
 - First, the number of non-consecutive days a store is out of stock (days OOS) is counted, starting with and including yesterday, over the alert horizon. The alert horizon is an alert parameter, Large OOS Horizon, defining the number of days over which calculations are performed for this alert. This parameter is maintained in the SRP Alert Maintenance workbook at the SKU/Store or Sub-Class/Company level.

- The days OOS is compared to a second alert parameter, Large Non-Cons. OOS Number of Non-Consecutive Days OOS. This parameter is maintained in the SRP Alert Maintenance workbook at the SKU/Store or Sub-Class/Company level. If the day OOS is greater than this parameter, the store is considered out of stock for non-consecutive days (OOS store).
 - To determine if the number of OOS stores is significant, a ratio (OOS ratio) is calculated as the number of OOS stores divided by the total number of stores for that SKU. The OOS stores are considered significant if the ratio is greater than an alert parameter, Large Non-Cons. OOS Alerting Stores Ratio. This parameter is maintained in the SRP Alert Maintenance workbook at the SKU/Store or SKU/Company level.
 - If the OOS ratio is greater than the Large Cons. OOS Alerting Stores Ratio, the first condition for this alert is true.
2. The Total sum of lost sales over horizon from the SKU/store(s) that satisfy the non-consecutive OOS threshold is greater than a set volume threshold.
 - First, total the lost sales over the alert horizon (Large OOS Horizon parameter) for the OOS stores.
 - The sum of lost sales is compared to an alert parameter, Large Non-Cons. OOS Corp. Lost Sales Volume over horizon (Large OOS volume). This parameter is maintained in the SRP Alert Maintenance workbook at the SKU/Store or SKU/Company level.
 - If the total lost sales for the OOS stores is greater than the Large OOS volume, this condition is true.
 3. If the SKU was out of stock last night for this store, condition 3 is true.
 4. If a Large Consecutive Out of Stocks alert was not generated for this SKU/store, condition 4 is true.

Large Out of Stocks Last Night

A Large Out of Stocks Last Night alert is generated when a significant number of stores are out of stock or a significant portion of possible sales yesterday are lost for a specific SKU or when the lost sales for the SKU at the company level is significant.

Only those stores that are out of stock (OOS) for the product last night will be alerted.

Stores alerted for Large Consecutive Out of Stocks or Large Non-Consecutive Out of Stocks will not be alerted.

Alert Parameters

- Large OOS Last Night Alerting Stores Ratio
- Large OOS Last Night Corp. Lost Sales % Possible Sales
- Large OOS Last Night Corp. Lost Sales Volume

Alert Logic Summarized

The Large Out of Stocks Last Night alert is triggered if condition 1 or 2 is true. In all cases, condition 3 and 4 must also be true:

1. Calculate the ratio of the number of stores out of stock last night (OOS stores) that against the number of stores ranged for that SKU. The calculated ratio must be greater than a user-defined threshold.

- To determine if the number of OOS stores is significant, a ratio (OOS ratio) is calculated as the number of OOS stores divided by the total number of stores for that SKU. The OOS stores are considered significant if the ratio is greater than an alert parameter, Large OOS Last Night Alerting Stores Ratio. This parameter is maintained in the SRP Alert Maintenance workbook at the SKU/Store or SKU/Company level.
 - If the OOS ratio is greater than the Large OOS Last Night Alerting Stores Ratio, the first condition for this alert is true.
2. Calculate the ratio total lost sales yesterday, taking in consideration all stores for the SKU, against their possible sales yesterday. The calculated ratio must be greater than a user-defined percentage.
 - First, the total lost sales yesterday (total LS yesterday) is calculated as the sum of lost sales yesterday for all stores ranged for that SKU.
 - The total possible sales yesterday (total PS yesterday) is calculated as the sum of possible sales yesterday for all stores ranged for that SKU.
 - To determine if the portion of possible sales yesterday is significant, a ratio (PS yesterday ratio) is calculated as total LS yesterday divided by total PS yesterday. The LS yesterday are considered significant if the ratio is greater than an alert parameter, Large OOS Last Night Corp. Lost Sales % Possible Sales. This parameter is maintained in the SRP Alert Maintenance workbook at the SKU/Store or (SKU/Company) level.
 - If the PS yesterday ratio is greater than the Large OOS Last Night Corp. Lost Sales % Possible Sales, condition 2 for this alert is true.
 3. The total of lost sales for all SKU/store(s) out of stock last night from is greater than a set volume threshold.
 - First, total the lost sales for this SKU at all stores from last night for the OOS stores.
 - The sum of lost sales is compared to an alert parameter, Large OOS Last Night Corp. Lost Sales Volume (Large OOS volume). This parameter is maintained in the SRP Alert Maintenance workbook at the SKU/Store or SKU/Company level.
 - If the total lost sales for the OOS stores is greater than the Last night OOS volume, this condition is true
 4. If a Large Consecutive Out of Stocks alert and a Large Non-Consecutive Out of Stocks alert were not generated for this SKU/store, condition 3 is true.

Day on Day Repeat Out of Stocks

A Day on Day Repeat Out of Stocks alert is generated when a significant number of stores that have been out of stock on the same day in consecutive weeks, and the amount of lost sales is above a threshold.

Only those stores that are out of stock (OOS) for the product last night will be alerted.

Stores alerted for Large Consecutive Out of Stocks or Large Non-Consecutive Out of Stocks will not be alerted.

Alert Parameters

- Day on Day OOS Horizon
- Day on Day OOS Day on Day Count Threshold
- Day on Day OOS Alerting Stores Ratio
- Day on Day OOS Corp. Lost Sales Volume

Alert Logic Summarized

The A Day on Day Repeat Out of Stocks alert is triggered if all of the following conditions are true:

1. Calculate the ratio of the number of stores out of stock (OOS) on the same day in consecutive weeks over the user-defined alert horizon for each SKU/store against the number of stores ranged for that SKU. The calculated ratio must be greater than a user-defined threshold.
 - First, count the number of days a store is out of stock repeat day on day (days OOS) for yesterday, yesterday - 7, yesterday - 14, over the alert horizon. The alert horizon is an alert parameter, Day on Day OOS Horizon, defining the number of days over which calculations are performed for this alert. This parameter is maintained in the SRP Alert Maintenance workbook at the SKU/Store or Sub-Class/Company level.
 - The days OOS is compared to a second alert parameter, Day on Day OOS Day on Day Count Threshold. This parameter is maintained in the SRP Alert Maintenance workbook at the SKU/Store or Sub-Class/Company level. If the day OOS is greater than this parameter, the store is considered day on day repeat out of stock (OOS store).
 - To determine if the number of OOS stores is significant, a ratio (OOS ratio) is calculated as the number of OOS stores divided by the total number of stores for that SKU. The OOS stores are considered significant if the ratio is greater than an alert parameter, Day on Day OOS Alerting Stores Ratio. This parameter is maintained in the SRP Alert Maintenance workbook at the SKU /Store or SKU /Company level.
 - If the OOS ratio is greater than the Day on Day OOS Alerting Stores Ratio, the first condition for this alert is true.
2. The total of lost sales for all Day on Day out of stock SKU/store(s) over the alert horizon is greater than a set volume threshold.
 - First, total the lost sales for this SKU at all Repeat Day on Day OOS stores over the alert horizon.
 - The sum of lost sales is compared to an alert parameter, Day on Day OOS Corp. Lost Sales Volume. This parameter is maintained in the SRP Alert Maintenance workbook at the SKU/Store or SKU /Company level.
 - If the total lost sales for the OOS stores is greater than the Day on Day OOS volume, this condition is true.
3. If the SKU was out of stock last night for this store, condition 3 is true.
4. If a Large Consecutive Out of Stocks alert and a Large Non-Consecutive Out of Stocks alert were not generated for this SKU/store, condition 4 is true.

Single Store Availability Problems

A Single Store Availability Problems alert is generated when a single store has been out of stock for more than a defined non-consecutive number of days, and the amount of lost sales is above a threshold.

Only those stores that are out of stock (OOS) for the product last night will be alerted.

Stores alerted for Large Consecutive Out of Stocks, Large Non-Consecutive Out of Stocks, Large Out of Stocks Last Night, or Day on Day Repeat Out of Stocks will not be alerted.

Alert Parameters

- Single Store Horizon
- Single Store Number of Days OOS
- Single Store Corp. Lost Sales Volume over Horizon

Alert Logic Summarized

Single Store Availability Problems alert is triggered if all of the following conditions are true:

1. The number days a store is out of stock (OOS), starting with and including yesterday, over the user-defined alert horizon must be greater than a user-defined threshold.
 - First, the number of non-consecutive days a store is out of stock (days OOS) is counted over the alert horizon. The alert horizon is an alert parameter, Single Store Horizon, defining the number of days over which calculations are performed for this alert. This parameter is maintained in the SRP Alert Maintenance workbook at the SKU/Store or Sub-Class/Company level.
 - The days OOS is compared to a second alert parameter, Single Store Number of Days OOS. This parameter is maintained in the SRP Alert Maintenance workbook at the SKU/Store or Sub-Class/Company level.
 - If the day OOS is greater than this parameter, the store is considered out of stock for non-consecutive days (OOS store).
2. The total sum of lost sales over horizon for the SKU/store that satisfy the OOS threshold is greater than a user-defined threshold.
 - First, total the lost sales over the alert horizon (Single Store Horizon) for the OOS store.
 - The sum of lost sales is compared to an alert parameter, Single Store Corp. Lost Sales Volume over Horizon (Single store volume). This parameter is maintained in the SRP Alert Maintenance workbook at the SKU/Store or SKU/Company level.
 - If the total lost sales for the OOS store is greater than the Single store volume, this condition is true.
3. If the SKU was out of stock last night for this store, condition 3 is true.
4. If Large Consecutive Out of Stocks, Large Non-Consecutive Out of Stocks, Large Out of Stocks Last Night, or Day on Day Repeat Out of Stocks alert were not generated for this SKU/store, condition 3 is true.

Historical Availability Summary Alert

A Historical Availability Summary Alert is raised when any alert in the Historic Availability Alerts Group is generated.

The summary alert allows the user to view stores with any historic alerts.

The Historical Availability Summary Alert is triggered if any of the following alerts are raised for a SKU/store:

- Large Consecutive Out of Stocks
- Large Non-Consecutive Out of Stocks
- Large Out of Stocks Last Night
- Day on Day Repeat Out of Stocks Alert
- Single Store Availability Problems

Projected Availability Alerts

Projected Availability Alerts provide notification of future conditions of forecasted conditions that could cause future stock problems for a store, such as project stock outs or low inventory, along with possible high inventory levels.

The following table lists projected availability alerts issued by SRP along with a brief description. Details for each alert are addressed in the following sections.

Alert	Description
High Projected Out of Stock	A High Projected Out of Stock alert is generated when a significant number of stores are projected to be out of stock or a significant portion of demand is projected as lost sales for a specific SKU and the projected lost sales for the SKU at the company level are significant.
High Projected Low Stocks	A High Projected Low Stocks alert is generated when a significant number of stores have projected inventory levels below a set threshold. Stores alerted for High Projected Out of Stock will not be alerted.
High Planned Orders	A High Planned Orders alert is generated when Planned orders for a single store exceed a threshold. Stores alerted for High Projected Out of Stock will not be alerted.
Projected Availability Summary Alert	A Projected Availability Summary Alert is raised when any alert in the Projected Availability Alerts Alert Group is generated. The summary allows the user to view any store with projected out of stocks or low stocks.

High Projected Out of Stock

A High Projected Out of Stock alert is generated when a significant number of stores are projected to be out of stock or a significant portion of demand is projected as lost sales for a specific SKU, and the projected lost sales for the SKU at the company level are significant.

Alert Parameters

- High Proj OOS / Low Stock Horizon
- High Proj OOS Number of Projected Days OOS
- High Proj OOS Alerting Stores Ratio
- High Proj OOS Corp. Lost Sales % Forecast
- High Proj OOS Corp. Lost Sales Volume over horizon

Alert Logic Summarized

The High Projected Out of Stock alert is triggered if condition 1 or 2 is true AND condition 3 is true:

1. Calculate the ratio of the number of stores where the total number of days projected out of stock (OOS), starting with and including today, over the user-defined alert horizon for each SKU/store against the number of stores ranged for that SKU. The calculated ratio must be greater than a user-defined threshold.

- Projected Lost Sales is calculated as demand plus customer orders, plus expected spoilage, minus projected inventory, minus expected receipts, minus user allocations, minus receipt plan.
 - The number of days a store is projected out of stock (projected days OOS) is counted over the alert horizon. The alert horizon is an alert parameter, High Proj OOS / Low Stock Horizon, defining the number of days over which calculations are performed for this alert. This parameter is maintained in the SRP Alert Maintenance workbook at the SKU/Store or Sub-Class/Company level.
 - The projected days OOS is compared to a second alert parameter, High Proj OOS Number of Projected Days OOS. This parameter is maintained in the SRP Alert Maintenance workbook at the SKU/Store or Sub-Class/Company level. If the projected days OOS is greater than this parameter, the store is considered projected out of stock (projected OOS store).
 - To determine if the number of projected OOS stores is significant, a ratio (projected OOS ratio) is calculated as the number of projected OOS stores divided by the total number of stores for that SKU. The projected OOS stores are considered significant if the ratio is greater than an alert parameter, High Proj OOS Alerting Stores Ratio. This parameter is maintained in the SRP Alert Maintenance workbook at the SKU/Store or (SKU/Company) level.
 - If the projected OOS ratio is greater than the High Proj OOS Alerting Stores Ratio, the first condition for this alert is true.
2. Calculate the ratio total projected lost sales, taking in consideration all stores for the SKU, against their demand forecast over the High Proj OOS / Low Stock Horizon. The calculated ratio must be greater than a user-defined percentage.
- First, the total projected lost sales (total projected LS) is calculated as the sum of projected lost sales, starting with and including today, over the alert horizon for all stores ranged for that SKU.
 - The total forecasted demand (total FD) is calculated as the sum of forecasted demand, starting with and including today, over the alert horizon for all stores ranged for that SKU.
 - To determine if the portion of demand is projected as lost sales is significant, a ratio (projected LS ratio) is calculated as total projected LS is divided by total FD. The projected LS are considered significant if the ratio is greater than an alert parameter, High Proj OOS Corp. Lost Sales % Forecast. This parameter is maintained in the SRP Alert Maintenance workbook at the SKU/Store or (SKU/Company) level.
 - If the projected LS ratio is greater than the High Proj OOS Corp. Lost Sales % Forecast, condition 2 for this alert is true.
3. The total projected lost sales for all SKU/store(s) are greater than a set volume threshold.
- The total projected LS (calculated above) are compared to an alert parameter, High Proj OOS Corp. Lost Sales Volume over horizon (High Proj OOS volume). This parameter is maintained in the SRP Alert Maintenance workbook at the SKU/Store or SKU /Company level.
 - If the total projected LS is greater than the High Proj OOS volume, this condition is true.

High Projected Low Stocks

A High Projected Low Stocks alert is generated when a significant number of stores have projected inventory levels below a set threshold.

Stores alerted for High Projected Out of Stock will not be alerted.

Alert Parameters

- High Proj OOS / Low Stock Horizon
- High Proj Low Stock Low Level Percentage
- High Proj Low Stock Number of Low Stock Days
- High Proj Low Stock Alerting Stores Ratio

Alert Logic Summarized

The High Projected Low Stocks alert is triggered if conditions 1 and 2 are true:

1. Calculate the ratio of the number of stores where the total number of days projected low stock, starting with and including today, over the user-defined alert horizon for each SKU/store against the number of stores ranged for that SKU. The calculated ratio must be greater than a user-defined threshold.
 - First, determine if a day is projected low stock by calculating the Receipt up to Level threshold (RUTL threshold) as RUTL multiplied by the user-defined alert percentage. The alert percentage is an alert parameter, High Proj Low Stock Low Level Percentage. This parameter is maintained in the SRP Alert Maintenance workbook at the SKU/Store level.
 - A day is considered projected low stock if the projected inventory (PI) is less than the RUTL threshold.
 - The number of days a store is projected low stock (projected days LS) is counted over the alert horizon. The alert horizon is an alert parameter, High Proj OOS / Low Stock Horizon, defining the number of days over which calculations are performed for this alert. This parameter is maintained in the SRP Alert Maintenance workbook at the SKU/Store or Sub-Class/Company level.
 - The projected days LS is compared to a second alert parameter, High Proj Low Stock Number of Low Stock Days. This parameter is maintained in the SRP Alert Maintenance workbook at the SKU/Store or Sub-Class/Company level. If the projected days LS is greater than this parameter, the store is considered projected low stock (projected LS store).
 - To determine if the number of projected LS stores is significant, a ratio (projected LS ratio) is calculated as the number of projected LS stores divided by the total number of stores for that SKU. The projected LS stores are considered significant if the ratio is greater than an alert parameter, High Proj Low Stock Alerting Stores Ratio. This parameter is maintained in the SRP Alert Maintenance workbook at the SKU/Store or (SKU/Company) level.
 - If the projected LS ratio is greater than the High Proj Low Stock Alerting Stores Ratio, the first condition for this alert is true.
2. If a High Projected Out of Stock alert was not generated for this SKU/store, condition 2 is true.

High Planned Orders

A High Planned Orders alert is generated when planned orders for a single store exceed a threshold.

Stores alerted for High Projected Out of Stock will not be alerted.

Alert Parameters

- High Planned Orders Weeks of Demand Multiple
- High Planned Orders Cases over Weeks Demand

Alert Logic Summarized

The High Planned Orders alert is triggered for a SKU/store when the next ATP day which has a release date greater than today (ATP day minus release schedule lead time is greater than today) has a significantly large order quantity. The High Planned Orders alert is triggered if all of the following conditions are true:

1. The planned order for a store for the next available to plan (ATP) day, with a release date greater than today, exceeds a user-defined multiple of the forecasted demand over the selected available to plan day plus 7.
 - First, calculate the total forecasted demand (total FD) as the sum of the forecasted demand from the selected ATP day through the next 7 days.
 - Calculate the factored demand by multiplying the total FD by the user-defined alert factor. The alert factor is an alert parameter, High Planned Orders Weeks of Demand Multiple. This parameter is maintained in the SRP Alert Maintenance workbook at the SKU/Store or Sub-Class/Company level.
 - If the store receipt plan for the first ATP day is greater than the factored demand, the first condition is true.
2. The planned order for a store for the next available to plan (ATP) day less total FD (defined above) is greater than a volume threshold.
 - Calculate the volume threshold by multiplying the store ordering packsize by the user-defined alert threshold. The alert threshold is an alert parameter, High Planned Orders Cases over Weeks Demand. This parameter is maintained in the SRP Alert Maintenance workbook at the SKU/Store or Sub-Class/Company level.
 - If the store receipt plan for the first ATP day less total FD is greater than the volume threshold, this condition is true.
3. If a High Projected Out of Stock alert was not generated for this SKU/store, condition 3 is true.

Projected Availability Summary Alert

A Projected Availability Summary Alert is raised when either the High Projected Out of Stock or High Projected Low Stocks alert is generated.

The summary allows the user to view any store with projected out of stocks, low stocks, or high planned orders.

The Projected Availability Summary Alert is triggered if any of the following alerts are raised for a SKU/store:

- High Projected Out of Stock
- High Projected Low Stocks

Other Alerts

Other Alerts are miscellaneous alerts which provide warning information not necessarily related to stocking levels.

The following table lists other alerts issued by SRP along with a brief description. Details for each alert are addressed in the following sections.

Alert	Description
Overstock	An Overstock alert is generated when Stock Cover and Projected Inventory for a store exceed overstock thresholds.
RDF Detail Alert	A Forecasting Detail exception is raised when an exception in RDF or another Forecasting system has been flagged for a SKU/Store.
No Like SKU Found	A No Like SKU Found exception is raised when there is a Store Like SKU value that is pointing to a SKU that is not in that domain.
High Repeated Dissipation	The alert indicates that a SKU/store has repeatedly had a significant amount of markdown sales and waste adjustments compared to its daily sales.
High Dissipation Yesterday	The alert indicates that, yesterday, a SKU had significant Dissipation (waste and markdown sales) compared to sales across a significant number of stores.

Overstock

An Overstock alert is generated when Stock Cover and Projected Inventory for a store exceed overstock thresholds.

Alert Parameters

- Stock Cover Days Threshold
- Overstock Units Threshold

Alert Logic Summarized

The Overstock alert is triggered if all of the following conditions are true:

1. The projected stock cover is greater than a user-defined stock cover days threshold.
 - First, calculate the projected Stock Cover Days as the count of days from today until the current day's Projected Inventory (PI) minus Forecast Demand (FD) is less than or equal to zero. If the PI minus FD is less than zero on the last day, calculate the percent of the last days demand that covers the current day's current day's PI.
 - The projected Stock Cover Days is compared to an alert threshold, Stock Cover Days Threshold. This parameter is maintained in the SRP Alert Maintenance workbook at the SKU/Store or Sub-Class/Company level.
 - If the projected Stock Cover Days is greater than the Stock Cover Days Threshold, the first condition is true.
2. The projected inventory in units is greater than the overstock units threshold.

- The projected inventory (PI) is compared to an alert threshold, Overstock Units Threshold. This parameter is maintained in the SRP Alert Maintenance workbook at the SKU/Store or Sub-Class/Company level.
- If the PI is greater than the Overstock Units Threshold, this condition is true.

RDF Detail Alert

A Forecasting Detail exception is raised when an exception in RDF or another Forecasting system has been flagged for a SKU/Store.

The RDF Detail Alert is loaded from an external source based on exceptions found in the user's forecasting system. No calculations are performed within SRP.

The RDF Detail alert is used to give the user visibility of an exception in the forecasting system that could be causing exceptions in SRP. This allows the user to determine if changes are required within the forecasting system or within SRP to resolve the exception.

No Like SKU Found

A No Like SKU Found exception is raised when there is a Store Like SKU value that is pointing to a SKU that is not in that domain.

During batch processing, AIP verifies that all Like SKU values are in the current domain. If there is a Store Like SKU value that is not a measure in that domain, an alert flag is triggered against the primary SKU/store.

High Repeated Dissipation

A High Repeated Dissipation alert is triggered when the number of days a store has high dissipation (Short Code Sales and waste adjustment), compared to daily sales, exceeds the threshold, and the threshold is exceeded at a percentage of stores. Yesterday must be included in one of the total days a store has high dissipation of a SKU.

High Dissipation Yesterday

A High Dissipation Yesterday alert is triggered when a store has high dissipation (short code sales and waste adjustment) compared to daily sales, and the ratio of high dissipation stores to all ranged stores exceeds the threshold. The stores must have high dissipation of the SKU yesterday and not be flagged as High Repeated Dissipation in order to be counted in the ratio and be alerted. Otherwise, the alert will trigger if the total dissipation percent of sales yesterday across all ranged stores exceeds the threshold.

Reviewing and Managing SRP Alerts

Alerts are used to drive the interactive process for the user to plan and manage store stocking levels and planned orders.


Reviewing and managing alerts for store replenishment plans involve the following components of the SRP solution:

- The Alert Manager
- The SRP Evaluation or Interactive Evaluation Workbook
- The SRP Maintenance Workbook
- The SRP Administration Workbook
- The SRP Alert Maintenance Workbook

The Alert Manager

When a user logs on to SRP, if any alerts have been issued to that user, the Alert Manager automatically opens. The Alert Manager displays all alerts issued to a user, along with other information, such as alert name and the number of instances for each alert, which will assist the user in prioritizing the alerts selected for review and management.

The Alert Manager is part of the common user interface for Retail Predictive Application Server (RPAS)-based products. This guide focuses on how you use the Alert Manager to review and resolve alerts in SRP. For more information about the Alert Manager, see the *RPAS User Guide* or the *RPAS Online Help*, which is accessible from the Help menu.



Alert Manager Window

About the Alert Tab

The Alert Manager's Alert tab displays all of the alerts that have been issued to a user and the workbooks in which the alerts occur. Alerts are displayed in the following format:

- **Category** – The category to which the alert belongs (in this case, SRP).
- **Alert Name** – A descriptive label for the SRP alerts described in the SRP Alerts portion of this chapter.
- **Priority** – The alert priority (High, Medium, or Low).
- **Status** – Specifies whether the alert is new since the last time the user logged on. If it is not new, it specifies whether the alert is resolved or unresolved.

Note: After selecting an alert from the list, a user can change the status of the alert by clicking the **Resolve Alert** button or the **Unresolve Alert** button.

- **Date** – The date that the alert was identified.
- **Count** – The number of SKU/Store combinations associated with the alert.

Alert Tab Buttons


The Alert tab displays the following buttons used for further processing on the alerts.

- **Resolve Alert/Unresolve Alert button** – For new alerts or alerts that you have reviewed; the Resolve Alert button changes the status of the alert from New or Reviewed to Resolved. For Resolved alerts, the Unresolve Alerts button changes the status back to Reviewed.
- **Insert Alert** – Selecting this button allows the user to insert the selected alert into the open workbook.
- **New Workbook** – Selecting this button allows a user to create a new workbook that includes the selected alert.
- **Open Workbook** – If you have existing alert workbooks, this button appears. It allows a user to open an alert workbook that was previously created. If no alert workbooks exist, this button is not displayed.

Analyzing and Resolving Alerts Using the Alert Manager and SRP Workbooks


The Alert Manager lists alerts issued to a user regarding potential problems that may require review. The user can select an alert, such as the Historical Availability alert to review and click **New Workbook** or **Open Workbook** to view more information about the alert.

1. If an alert workbook was previously created, select **Open Workbook**. If no alert workbook was previously created, select **New Workbook** can be selected. The Alert wizard screen appears to guide through creating a new alert workbook. .




Alert Manager– Select Optional Alerts Screen

2. Select any additional alerts that you want to include in the new workbook, and click **Next**. The Select Workbook Template screen appears.



Alert Manager– Select Workbook Template Screen

3. Select the workbook template that you want to use to build the workbook, and click **Next**. Typically, the SRP Interactive Evaluation workbook will be selected. The Select Hierarchy screen appears.



The image shows a screenshot of the 'Alert Manager' application window. The title bar is blue with the text 'Alert Manager' and a red close button. The main area has a light beige background. It contains two sections for selecting hierarchies. The first section is titled 'Please select hierarchies to range.' and has a list box with 'None', 'Product', and 'Location'. 'Product' is selected. The second section is titled 'Please select hierarchies to hide.' and has a list box with 'None', 'Product', and 'Location'. 'None' is selected. At the bottom, there are five buttons: 'Cancel', '<Back', 'Next>', 'Finish', and 'Help'.

Alert Manager

Please select hierarchies to range.

None
Product
Location

Please select hierarchies to hide.


None
Product
Location

Cancel <Back Next> Finish Help

Alert Manager– Select Hierarchies Screen


4. Select hierarchies for the new workbook and click **Next**. In most cases, both product and location hierarchies should be selected. At this time, the wizard for the workbook template that was selected is displayed. The Available SKUs screen appears.

Note: When a hierarchy is selected, only positions in the hierarchy that triggered an alert will be available for selection in the new workbook wizard. For instance, when selecting the product hierarchy, the product selection screen for the new workbook wizard will only allow you to choose products for which an alert was triggered. This means that all non-alert-related positions will be excluded from the workbook build.




Alert Manager – Available SKUs

5. Select the SKU(s) that you want to view to in the workbook, and click **Next**. The Available Stores screen appears.



Alert Manager – Available Stores Screen

6. Select the store(s) that you want to view to in the workbook, and click **Next**. The Available Days screen appears.



The screenshot shows the 'Alert Manager' window with the 'Available Days' tab selected. The window has a blue title bar with the text 'Alert Manager' and a close button. The main area is divided into two panes. The left pane, titled 'Available Days', contains a list of dates from 04/01/06 to 04/19/06, each with a red checkmark. The right pane, titled 'Selected Days', contains a list of the same dates, each with a black dot. Below the panes is a checkbox labeled 'Synchronize hierarchies'. At the bottom of the window are five buttons: 'Cancel', '<Back', 'Next>', 'Finish', and 'Help'.

Available Days	Selected Days
☒ 04/01/06	● 04/01/06
☒ 04/02/06	● 04/02/06
☒ 04/03/06	● 04/03/06
☒ 04/04/06	● 04/04/06
☒ 04/05/06	● 04/05/06
☒ 04/06/06	● 04/06/06
☒ 04/07/06	● 04/07/06
☒ 04/08/06	● 04/08/06
☒ 04/09/06	● 04/09/06
☒ 04/10/06	● 04/10/06
☒ 04/11/06	● 04/11/06
☒ 04/12/06	● 04/12/06
☒ 04/13/06	● 04/13/06
☒ 04/14/06	● 04/14/06
☒ 04/15/06	● 04/15/06
☒ 04/16/06	● 04/16/06
☒ 04/17/06	● 04/17/06
☒ 04/18/06	● 04/18/06
☒ 04/19/06	● 04/19/06

☐ Synchronize hierarchies

Cancel <Back Next> Finish Help

Alert Manager – Available Days Screen

7. Select the day(s) that you want to view to in the workbook, and click **Finish**.

The SRP Interactive Evaluation workbook is opened. Only those SKU/Store(s) that are associated with the selected alert are displayed in the Replenishment Summary worksheets. Checkmarks identify the positions associated with a recognized alert.

Location	Product
S303 - MISHAWAKA IN	100038065 - CALCULATC
Like SKU	
Like SKU End Date	
Off-Supply Effective Date	1/1/2007
On-Supply Effective Date	4/1/2006
Projected Stock Out	355.00
Projected Stock Out - What If	45.00
RDF Detail Alert Count	0
RDF Detail Alert Mask	☒
SRP RDF Detailed Alert	☐
Store Current Inventory	210.00
Store End Date Range	
Store End Date Range (expanded)	4/1/2006
Store Overstock Alert	☒
Store Repl Subtype Code	
Store Repl Type Code	

Example of the Store Overstock Alert for the SRP Replenishment Plan (SKU/Store) Workbook

8. Analyze the selected workbook and, if necessary, make the appropriate changes.
 After selecting a SKU to work with a user can look for patterns that may be causing the exception, such as stocking and inventory issues, issues with SRP parameters, threshold values, or problems in the demand forecasts fed from the user's forecasting system.
 Suppose a Historical Availability alert was selected and for this SKU/Store combination, the Historical Availability was triggered by the Single Store Availability Problems alert. The user can review the SRP Replenishment Summary worksheet to determine when the exception occurred and its cause.

Analysis may show the SKU/Store was out of stock for a variety of reasons, such as:

- The supplier was unable to deliver the product to the location in time
- A warehouse was unable to fulfill the store's demand on the dates indicated
- An SRP parameter value was not properly set
- Data loaded into SRP is not accurate

At this point, the user can look at the different views of replenishment plan data in the workbook to find any patterns and the root cause of the problem. Correcting the problem could require changes to parameters or actions outside of AIP, such as communication with the supplier.

When reviewing the measures, the user may consider the following questions:

- Is the problem source in external data that feeds into SRP? For example, is SRP receiving a bad or inconsistent demand forecast?
- Is the problem within SRP itself? Is the problem in values for store replenishment parameters set within SRP, such as the replenishment method for the product or products and other parameters, Safety Stock, and other measures?

If it has been determined the problem is with SRP, in addition to reviewing the replenishment plan data, the SRP Interactive Evaluation workbook can be used to perform "what-if" analysis, using various replenishment parameters to determine which parameters provide the desired results.

The parameters can be maintained directly in the Interactive Evaluation workbook or in the SRP Maintenance workbook. The parameters may also be maintained at higher levels in the SRP Administration workbook. Refer to the workbook chapter in this document for detailed information on these workbooks.

It may be determined that the problem is thresholds or other alert parameters for triggering alerts need tuning. For example, a threshold may need to be increased or decreased, either as a temporary change or as a deliberate change in how the business handles that exception.

The alert parameters can be maintained in the SRP Alert Maintenance Workbook at the SKU/Store, SKU/Company, or Sub-class/Store levels. Refer to the workbook chapter in this document for detailed information on this workbook.

Note: Changes to SRP replenishment parameters or alert parameters will be reflected in the next AIP batch run.

Once the review, analysis, and any desired changes have been made, the alert status may be updated to 'resolved'.

9. To resolve, or close, an alert, return to the Alert Manager. Select the alert that you investigated, and click the **Resolve Alert** button. This moves the alert to the Resolved state.

Note: At any point in the alert review process, if you acquire new information about an alert that would move it back to open or unresolved status, you can select the alert, and click the **Unresolve Alert** button.

Loading and Maintaining Data

To generate a store replenishment plan, key data must be must first be loaded into AIP from various sources, including external sources and Data Management (DM)

Data Required

The following data is required for SRP:

- Basic Hierarchies and Attributes
- Demand Forecast
- Demand Forecast Error
- Current Store and Warehouse Inventories
- On Order and In Transit Information
- Customer Orders
- E-commerce orders
- Key item information (pack size, cases per pallet, and promotions)
- Delivery schedules and lead-times

Within SRP, several key replenishment parameters are required to generate a store replenishment plan. The user can maintain these parameters at various levels in the hierarchy:

- Global parameters are entered at the department level. This will be the highest default level used in determining the effective value of the measure. In other words, the parameter values at the department level will only be used if no lower level (Sub-class/Store Format or SKU/Store) parameters exist.
- Default Parameters are entered at the Sub-class/Store Format level. This is the second and middle default level used in determining the effective value of the measure. In other words, the parameter values at the Sub-class/Store Format level will only be used if no lower level (SKU/Store) parameters exist. Parameter values at the Sub-class/Store Format level will be used over department defaults.
- Exception parameters are entered at the SKU/Store level. This is the lowest level used in determining the effective value of the measure. In other words, exception parameters the will be used over department and Sub-class/Store Format defaults.
- The default parameters allow the user to enter parameters that will affect many SKUs. Defaults can be used to set up basic replenishment parameters to meet the objectives of the business. These defaults can then be tweaked at the lower levels, to meet specific needs of a SKU/Store.

Many of the exception level parameters are also time-phased by day or week, allowing the user to change parameters prior to the actual date the change is effective.

Adding a New Store Using a Sister Store

Before opening a new store, the new store may be added to the system and replenishment planning can begin. A new store can be modeled after a store with similar characteristics and anticipated similar sales. To do this, a “Sister Store” relationship is set up in RMS or a legacy system. Once this relationship is established, SRP will perform a one-time copy of all required replenishment settings and parameters from the sister store. SRP will perform a weekly copy of sales history from the sister store to a new store that is scheduled to open. It will continue to copy the sales history weekly up until the Store Opening Date

Adding a New SKU Using a Like SKU

Some of the SRP Replenishment methods use sales history to calculate the inventory targets and allocation boundaries. Since a new SKU has little or no sales history, the user has the ability to link the new SKU to an existing or “Like” SKU. A “Use Like SKU” flag indicates whether or not to use the Like SKU. An effective end date for the Like SKU allows the user to set a date when the new SKU’s sales history will be deemed stable enough to use.

The Like SKU functionality can also be used for existing products when the sales history does not reflect current trends.

A Like SKU is set up in the SRP Interactive Evaluation Workbook, SRP Replenishment Plan (SKU/Store) Worksheet for the “target” SKU to which the history is to be copied. On this worksheet, the user may enter the Like SKU and its parameters. The Like SKU must be in the same domain as the target SKU.

Glossary

Active Product

Product that is for sale.

Actuals

Figures for sales, receipts and inventory for product/ locations.

Advanced Inventory Planning (AIP)

A suite of software products that are designed to manage the supply chain needs of large retailers, from interaction with its suppliers through various layers of warehouses down to individual stores and e-commerce sites. It couples time-phased replenishment and allocation algorithms to produce an actionable receipt plan over time. This is based on demand forecasts, replenishment parameters, and inventory availability at the numerous supply points within the supply chain. The suite is composed of Store Replenishment Planning (SRP), Warehouse Replenishment Planning (WRP), Order Management (OM), and Data Management (DM).

Alert

A notice that is displayed to system users that a value is above or below user defined limits (an exception).

Alert Manager

A window that displays the alerts that are assigned to you. This dialog provides a list of all identified instances in which a monitored data value fall outside a set of defined limits. You may pick an alert from this list and have the Alert Manager automatically build a workbook that contains the measure values that triggered the alert.

Alert Workbooks

Workbooks that display all of the alerts that have been issued to you along with the workbooks in which the alerts occur.

Availability Lead Time

This refers to the number of days from receipt that an order is prepared to be shipped to the next level in the supply chain. Valid values are 0 and 1.

Collaboration

A process of exchanging forecasted and actual sales, order, and other data between trading partners.

Commodity

The level at which plans will be created for the stores. Commodity is synonymous with product and SKU.

Commodity Pack-Size

Numeric value that indicates the pack-size that may be ordered for a given commodity. Commodity Pack-Size is synonymous with SKU Pack-Size.

Constrained Receipt Plan

The ideal receipt quantity is modified to account for the availability of a product at the source location.

Corporate Acceptable Loss

The threshold for the amount of stock that is acceptable to lose due to spoilage. This amount is determined at a corporate level, and it affects measures, such as SRP Ideal Receipt Quantity.

Corporate Discontinuation Date

A date that represents when a SKU pack-size is planned for discontinuation at the corporate level.

Coupled

An information only flag to indicate a placement lead-time is in effect for this SKU. The coupled flag is not used in any calculations and does not determine that the placement lead-time is used.

Data Modeling

When setting up a new element, such as a new store, the user can select a similar store and use most of the characteristics of that store as a model for the new store.

Decoupled

An information only flag to indicate a placement lead-time is not in effect for this SKU. The decoupled flag is not used in any calculations and does not determine that the placement lead-time is not used.

Delivery Calendar Exception

A delivery lead-time that is used instead of the “normal” delivery lead-time. The lead-time is a numeric value.

Demand Group

A grouping of similar SKU pack-sizes used in DM to apply changes for all SKU pack-sizes in the demand group.

Demo Stock

The amount of stock to be used as demos (floor models), although it may be sold.

Direct Supplier

A supplier that ships a product directly to a store, thereby bypassing layers of the supply chain.

Dynamic Replenishment Method

A replenishment method that attempts to replenish only the quantity that is required from one replenishment cycle to the next. This method is useful for minimizing the amount of stock on hand while preventing stock-outs. It considers the lead times of the product and forecast prediction intervals for the safety stock calculations.

Exception

A value that is greater than or less than a user-defined limit.

Exception Reporting

The process of notifying the user that exceptions exist.

Fixed Period

The future time period in which a user can no longer alter an order that has been placed.

Forecast Data

Information about a store's future demand. In SRP, this data is often referring to data that has originated from Retail Demand Forecasting (RDF).

Forecasted Demand

The quantity of an item forecasted to be sold during a specified period.

Global Non-release Day

A day when orders, except for exceptions, are not released.

Global Non-trading Day

A day when all stores are not open to trade.

Hierarchy Information

Information from or about data structures (hierarchies), such as product, location, or time.

Home Warehouse

This is the warehouse within the profile that will normally, but not always, supply all of the products from the profile to the selected store. Usually, this is the warehouse geographically closest to the store.

Hybrid Replenishment Method

A replenishment method that is a combination of Dynamic and Time Supply replenishment methods. The main difference between the Hybrid and Dynamic methods is the calculation of safety stock. In the Hybrid method, two choices are available to calculate safety stock. The safety stock is calculated by summing the forecasted demand over minimum days of time supply or multiplying an average rate of sale by minimum days of time supply. The result is compared to the safety stock minimum level and adjusted up to the minimum level if required.

Ideal Store Receipt Plan

A receipt plan that is generated after the data is loaded. The parameters set for a particular replenishment method for a particular product/store combination are used to drive the calculations that will generate the initial receipt plan. This process considers items; such as product life, rounding constraints, and pack-sizes to determine the ideal receipt quantities over time for each product/store combination.

In Transit

The number of items that have been ordered, picked up, and shipped, but not yet received at the replenished location.

Item

A generic term for any uniquely identifiable SKU in the merchandise hierarchy.

Lead Time Cycle

A cycle of 1, 2, or 4 weeks that specifies the lead-time for an order group on a specific day of the period.

Location Hierarchy

Pre-defined list of stores that is based on attributes; such as size of store, climate, and type of store. There will also be a list of supply points.

Lost Sales

The estimated number of historical or projected sales that are lost due to stock outs. Lost sales are used in calculating SRP alerts.

Maximum Limit

The maximum amount of a USA a store or store group is able to receive.

Min/Max Replenishment Method

A simple, non-forecast-based replenishment method that should only be used when it is impossible to generate a reasonable forecast, such as a completely new type of product that cannot be modeled after anything else or for extremely slow-selling items where the minimum presentation levels constantly exceed the weekly demand.

Minimum Limit

The minimum amount of a USA that a store or store group is able to receive.

Need

The quantity of a product that represents the inventory demand when considering the defined data at the location level.

Net Inventory

Inventory that has been “committed” to a replenished location. This includes items on hand, on order, and in transit.

Network Group

A grouping of profiles/warehouses that are used for monitoring the quantities of products that are flowing through the physical network. One profile can only be in one network group at any given point in time unless there are warehouse exceptions within a profile. A network group can contain many profiles.

No Replenishment Method

A replenishment method that is provided for cases when replenishment calculations need to be turned off for a specific SKU/store/day. This method is used for periods when a store does not want to have any replenishment performed.

Non-Delivery Day

The day that a store cannot receive a delivery.

Non-Order Day

The day that a store or a regional distribution center cannot release an order.

Off-Supply Date

The date that represents the final date for delivery of a product into a store.

On Hand

The current inventory (in units) of a given product at a replenished location.

On-Supply Date

The date that represents when a store should begin receiving the product.

Open Orders

The number of items that have been ordered, but not yet shipped.

Order Calendar

A calendar of how many days in advance an order must be placed to be received on a specific day of the period. This calendar is generally produced by repeating an order cycle.

Order Cycle

A cycle of 1, 2, or 4 weeks that specifies how many days in advance an order must be placed to be received on a specific day of the period.

Order Cycle Pattern Length

The length of the order cycle in number of weeks (1, 2, or 4).

Order Group

A group that has similar order placement/lead-time characteristics. These characteristics include order cycles.

Order Lead Time

The number of days between the date an order is placed and the date that the merchandise is available for sale in the store.

Order Up To Level

See Receive Up To Level.

Pallet

A wooden platform that is used for handling, storing, or moving inventory throughout the supply chain.

Parameter Maintenance

The process that is used to set up or update the default values that are used to populate measures and exception thresholds.

Pattern

Patterns are used for placing and releasing orders to WRP and PKMS. Each commodity store combination is allocated a pattern. Patterns may change over time or as a result of switching the commodity to a different profile.

Placement Calendar

A schedule of the date that an order must be released by a store in order for the store to receive it by a certain date. The order must move through the entire supply chain (supplier to store).

Placement Cycle

A cycle of 1, 2, or 4 weeks that specifies how many days in advance an order must be placed from a store to a supplier for it to be received on a specific day of the period.

Placement Lead Time

The placement lead-time indicates that SRP cannot change the order plan after a specified number of days prior to the delivery day.

Planning Group

A single or a collection of network groups. Planning groups enable Network controllers to have a high level view of the volumes that flow through the supply chain and identify any capacity issues at warehouses.

Planning Horizon

The range of planning involved. This is typically expressed as a range of dates (for example, 1-35 days or 1-26 weeks).

Presentation Stock

The amount of stock that must be on store shelves in order to make the merchandise fixture look attractive. Presentation stock is not expected to satisfy consumer demand, but it can be used to do so.

Product

The level at which plans will be created for the stores. Product is synonymous with commodity and SKU.

Product Hierarchy

A pre-defined list of items that are grouped on similar attributes.

Product Type

All commodities products will have a product type (specified in RMS, such as Ambient, Chill, Frozen, or Slow Moving goods), and the product types are linked to a chamber.

Profile

Grouping of products with similar ordering patterns. The profile assists in defining the sourcing rules for a commodity between store and warehouses.

Proportional Spreading

This refers to the ability to change a value at an aggregated level, such as class, and have that value spread to the lower levels of detail while maintaining the relationship that each one is to the total.

Ranged Product

A product that is currently being sold.

Ranging

To specify ranges of positions in a hierarchy over which you want to apply an alert. For example, you might only want one subclass of products (and not the entire product hierarchy) to be monitored by a particular alert.

Rate of Sale

An average measure of how fast inventory is sold over a specified time period. In time supply replenishment, ROS is multiplied by the minimum and maximum days of stock values to calculate stocking levels for the time supply window. Also see Time supply replenishment method.

Receipt Point

The inventory level that triggers a suggested order.

Receive Up To Level

The maximum value to which a chosen replenishment method will raise the inventory when generating a recommended orders. Receive Up To Level is synonymous with Order Up To Level.

Receiving Schedule

A Boolean measure that indicates when stores can receive a delivery.

Recommended Order Quantity

The total number of units that the system suggests should be ordered for a given product/location combination.

Reconciliation

Strategic placement of merchandise to either store locations or warehouse locations.

Reconciliation Adjustment

The difference between the ideal order quantity and the constrained order due to product availability at the source.

Reconciliation Period

A period of time within the fixed period over which the reconciliation process occurs based on availability of inventory and demand.

Reconciliation Quantity

The suggested quantity to be allocated to each location or location group. This is based on the need and the defined quantity limits. This quantity can be over-written by the user prior to approving.

Regional Distribution Center (RDC)

A stockholding location that is used to distribute goods to stores or other warehouses within a given region. Also see warehouse.

Release Calendar

A schedule of what date an order must be released by in order to receive it by a certain date. Same as a release schedule.

Release Calendar Exceptions

A release lead-time that is used instead of the “normal” release lead-time. The lead-time is a numeric value.

Release Cycle

A cycle of 1, 2, or 4 weeks that specifies how many days in advance an order must be placed from a store to a warehouse for it to be received on a specific day of the period.

Release Date

The date that store order goods must leave the warehouse in order to arrive at the store as planned.

Release Schedule

A schedule of the date that an order must be released in order to receive it by a certain date.

Replenishment

A pull method of deploying merchandise to locations that is used for staple products that have a predictable demand, a frequent reorder period, and a base inventory level.

Replenishment Cycle

The set of events that make up one iteration of the replenishment process. For instance, Order Lead Time followed by Review Time followed by Inventory Selling Days.

Replenishment Parameters

Values that are stored to populate measures and exception thresholds specifically related to replenishment.

Replenishment Plan

A unique set of data (calculated according to demand forecasts), replenishment parameters, and inventory availability that gives retailers the ability to project their demand and share these projections with their suppliers whenever it is appropriate.

Retail Demand Forecasting (RDF)

Oracle Retail's statistical and causal forecasting solution. RDF uses state-of-the-art modeling techniques to produce high quality forecasts with minimal human intervention. Forecasts produced by RDF enhance the retailer's supply chain planning, allocation, and replenishment processes.

Retail Merchandising System (RMS)

Oracle Retail's transaction system that serves as the focal point for information flows throughout the Oracle Retail Product Suite. This has key functions; such as inventory management, purchasing and receiving, price/ promotion management, and replenishment.

Retail Predictive Planning

New generation planning suite that provides solutions that are easy to use, flexible, and in support of all aspects of an organization's planning process.

Review Time (RT)

The amount of time (measured in days) that represents the amount of time between days on which an order may be generated.

Rule

The foundation for USAs is based on the "need" that defines the data to determine the individual store need based on user-defined rules. Rule modifiers can be applied to the selected rule to further increase the accuracy of the need calculation. There are four Rules to choose from:

1. Sales History
2. Forecasted Orders
3. Forecasted Sales
4. Manual Index

Rule Modifier

A defined set of data that enables a more accurate calculation of allocation quantity (for example, time definition).

Safety Stock

The number of units to have on hand in order to ensure that enough items are ordered to cover deviations from forecasted demand.

SKU

Stock Keeping Unit. A SKU is a number that is associated with a product for inventory purposes. Also see Product.

Source Switching

The process of moving a supply point for a product/store combination. Switching is used to balance the quantities of commodities that are flowing through the system (for example, Christmas). It is also used for resolving Warehouse supply problems. There are two types of switches: temporary and permanent.

Store Calendar

Boolean measure that indicates when stores can receive a delivery.

Store Demand Forecast Data

Information about a store's future demand. In SRP, this data is often referring to data that is originating from Retail Demand Forecasting (RDF).

Store Format

A grouping of stores with a similar layout. Examples include Local, Supermarket, and Super Center.

Store Placement Lead Time

The time that a product takes to get from the supplier to a store from the order date.

Store Release Lead Time

The time that a product takes to get from a RDC to a store from the order date.

Store Replenishment Plan

A unique set of data (calculated according to demand forecasts) replenishment parameters, and inventory availability that gives retailers the ability to project their demand and share these projections with their suppliers whenever it is appropriate.

Store Replenishment Planning (SRP)

A component of the Oracle Retail Advanced Inventory Planning solution. It uses a set of parameters and calculations on loaded static and dynamic data to produce a replenishment receipt plan at the store level.

Store Shipping Lead Time

The number of days between the date an order is shipped and the date it is expected to be received in the store.

Supplier

The top level in the Retailer supply chain. This is the first level, which is not always owned and operated by Retailer.

Supplier Order Multiple

The quantity of units that must be ordered at the same time.

Supply Point

The source from where the ordering location will receive its inventory from.

Time Supply Horizon (TSH)

An optional measure that determines the number of days used to calculate the rate of sale from forecast data. If a TSH is not specified, forecasts are simply summed over the minimum and maximum days of supply.

Time Supply Replenishment Method

A replenishment method that allows users to maintain a minimum and maximum amount of stock in terms of days of supply. This method is useful for replenished items where the objective is not necessarily to reduce the inventory on hand, but to prevent stock-outs and maintain a constant inventory within a specified range.

Unconstrained Receipt Plan

The ideal receipt quantity based on the current inventory position, the receipt point, and the receive up to level allocation boundaries.

Unit of Measure

Defines how the user views data — either in packs or eaches.

User Specified Allocation (USA)

A component of the Store Replenishment Planning (SRP) solution that allows for system users to 'push' inventory to a given store or a group of stores.

Value Added Product

A promotional product that includes an addition amount of the product for the same price as the un-promoted product.

Warehouse

A stockholding location that is used to distribute goods to stores or other warehouses within a given region. Also see Regional Distribution Center.

Warehouse Chamber

Grouping of products with the same storage characteristic or distribution channels (WH-CH). For example, Ambient, Chill, Frozen, or Slow Moving goods.

Warehouse Replenishment Planning (WRP)

A component of the Oracle Retail Advanced Inventory Planning solution that determines the orders between depots and suppliers while constraining each depot's orders based on product availability at its source. Supplier orders are not constrained.

Warehouse Inventory

The quantity of merchandise that is owned in perpetual inventory residing in the warehouse for eventual distribution to store locations or other warehouse locations.

Wizard

Used to select a product, locations, set of rules, rule modifiers, and periods of time.