

# Oracle® WebLogic Server

Configuring and Managing the WebLogic Messaging Bridge

10g Release 3 (10.3)

July 2008

ORACLE®

Copyright © 2007, 2008, Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this software or related documentation is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, the following notice is applicable:

U.S. GOVERNMENT RIGHTS Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, duplication, disclosure, modification, and adaptation shall be subject to the restrictions and license terms set forth in the applicable Government contract, and, to the extent applicable by the terms of the Government contract, the additional rights set forth in FAR 52.227-19, Commercial Computer Software License (December 2007). Oracle USA, Inc., 500 Oracle Parkway, Redwood City, CA 94065.

This software is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications which may create a risk of personal injury. If you use this software in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure the safe use of this software. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software in dangerous applications.

Oracle is a registered trademark of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners.

This software and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

# Contents

## 1. Introduction and Roadmap

Document Scope and Audience . . . . .	1-1
Guide to This Document . . . . .	1-2
Related Documentation . . . . .	1-2
Samples and Tutorials for the JMS Developer . . . . .	1-2
Avitek Medical Records Application (MedRec) and Tutorials . . . . .	1-3
JMS Examples in the WebLogic Server Distribution . . . . .	1-3
Additional JMS Examples Available for Download . . . . .	1-3
New and Changed Features in This Release . . . . .	1-3

## 2. Understanding the Messaging Bridge

What Is a Messaging Bridge? . . . . .	2-1
Messaging Bridge Components . . . . .	2-2
Resource Adapters . . . . .	2-2
Source and Target Bridge Destinations . . . . .	2-6
Messaging Bridge Instance . . . . .	2-6
Configuring and Managing a Messaging Bridge . . . . .	2-6
Create a Messaging Bridge Instance . . . . .	2-7
Manage a Messaging Bridge Instance . . . . .	2-7

## 3. Designing a Messaging Bridge

When to use a Messaging Bridge . . . . .	3-1
Store and Forward Messaging . . . . .	3-2

Replicating a Topic . . . . .	3-2
When to Avoid using a Messaging Bridge . . . . .	3-2
Selecting a Quality-of-Service (QOS) Level . . . . .	3-3
Messaging Persistence. . . . .	3-4
Message Ordering . . . . .	3-4
Setting the Number of Connection Factories . . . . .	3-4
Preserving Message Properties . . . . .	3-5
Using the JMSXUserID Property with a Messaging Bridge. . . . .	3-6
Using Distributed Destinations as Source and Target Destinations . . . . .	3-6
Tuning a WebLogic Messaging Bridge . . . . .	3-7

## 4. Interoperating with Different WebLogic Server Releases or Foreign Providers

Interoperating with Different WebLogic Server Releases . . . . .	4-1
Naming Guidelines for WebLogic Servers and Domains . . . . .	4-1
Configuring Interoperability for WebLogic Domains . . . . .	4-2
Configuring Interoperability for Exactly-once QOS . . . . .	4-2
Configuring At-least-once or At-most-once QOS . . . . .	4-3
Interoperating with Foreign Providers . . . . .	4-3

## 5. FAQs: WebLogic Messaging Bridge

Why did the messaging bridge fail to connect to the source bridge destination?	5-2
Can the messaging bridge handle two-phase or global transactions between separate WebLogic Server domains or between different releases?	5-2
I configured the messaging bridge to use the Exactly-once quality of service for two-phase transactions. So why am I getting a “quality of service is unreachable” error?	5-3

Can a messaging bridge to automatically downgrade the quality of service if the Exactly-once service isn't available on either the source or target bridge destination? . . . . .	5-3
I deployed the transactional <code>jms-xa-adp.rar</code> resource adapter on domain where the message bridge is running, but I still get a "failed to find bridge adapter" message? . . . . .	5-4
When configuring a source or target messaging bridge destination, do I need to set the Adapter Classpath field? . . . . .	5-4
How do I enable debugging for the messaging bridge? . . . . .	5-4
What do the messaging bridge monitoring states indicate on the Monitor Messaging Bridge console page? . . . . .	5-5
Is there another way to monitor the messaging bridge without using the Administration Console? . . . . .	5-6
Can the messaging bridge use distributed destinations as source and target destinations? . . . . .	5-6



# Introduction and Roadmap

The following sections describe the contents and organization of this guide—*Configuring and Managing the WebLogic Messaging Bridge*:

- [“Document Scope and Audience”](#) on page 1-1
- [“Guide to This Document”](#) on page 1-2
- [“Related Documentation”](#) on page 1-2
- [“Samples and Tutorials for the JMS Developer”](#) on page 1-2
- [“New and Changed Features in This Release”](#) on page 1-3

## Document Scope and Audience

This document is a resource for system administrators who want to configure and manage a WebLogic Messaging Bridge as a forwarding mechanism between any two messaging products—thereby providing interoperability between separate implementations of WebLogic JMS, or between WebLogic JMS and another messaging product. It also contains information that is useful for business analysts and system architects who are evaluating WebLogic Server® or considering the use of WebLogic Server JMS for a particular application.

It is assumed that the reader is familiar with programming in Java Platform, Enterprise Edition (Java EE) and JMS concepts. This document emphasizes the value-added features provided by WebLogic Server and key information about how to use WebLogic Server features and facilities to configure and manage a messaging bridge.

## Guide to This Document

- This chapter, [Chapter 1, “Introduction and Roadmap,”](#) describes the organization and scope of this guide, as well as new features and related documentation.
- [Chapter 2, “Understanding the Messaging Bridge,”](#) describes basic WebLogic Messaging Bridge resources, such as resource adapters and destinations.
- [Chapter 3, “Designing a Messaging Bridge,”](#) explains design options and other prerequisite considerations for configuring a WebLogic Messaging Bridge.
- [Chapter 4, “Interoperating with Different WebLogic Server Releases or Foreign Providers,”](#) explains the interoperability guidelines that apply when using the messaging bridge to access JMS destinations on different releases of WebLogic Server and in other WebLogic Server domains.

## Related Documentation

For information on topics related to configuring and managing a messaging bridge, see the following documents:

- [Configuring and Managing WebLogic JMS](#) is a guide to configuring and managing WebLogic JMS resources.
- [Programming WebLogic JMS](#) is a guide to developing WebLogic JMS applications.
- [WebLogic Server Performance and Tuning](#) provides information on how to monitor performance and tune the components in a WebLogic Server.
- [Developing Applications with WebLogic Server](#) is a guide to developing WebLogic Server applications.
- [Deploying Applications to WebLogic Server](#) is the primary source of information about deploying WebLogic Server applications.
- [Programming WebLogic Resource Adaptors](#) contains information on WebLogic resource adapters and the WebLogic Server implementation of the Java EE Connector Architecture.

## Samples and Tutorials for the JMS Developer

In addition to this document, Oracle provides a variety of code samples and tutorials for JMS developers. The examples and tutorials illustrate WebLogic Server JMS in action, and provide practical instructions on how to perform key JMS development tasks.



Oracle recommends that you run some or all of the JMS examples before developing your own EJBs.

## Avitek Medical Records Application (MedRec) and Tutorials

MedRec is an end-to-end sample Java EE application shipped with WebLogic Server that simulates an independent, centralized medical record management system. The MedRec application provides a framework for patients, doctors, and administrators to manage patient data using a variety of different clients.

MedRec demonstrates WebLogic Server and Java EE features, and highlights Oracle-recommended best practices. MedRec is included in the WebLogic Server distribution, and is accessed from the Start menu on Windows machines. For Linux and other platforms, start MedRec from the `WL_HOME\samples\domains\medrec` directory, where `WL_HOME` is the top-level installation directory for WebLogic Platform.

MedRec includes a service tier comprised primarily of Enterprise Java Beans (EJBs) that work together to process requests from web applications, web services, and workflow applications, and future client applications. The application includes message-driven, stateless session, stateful session, and entity EJBs.

## JMS Examples in the WebLogic Server Distribution

WebLogic Server optionally installs API code examples in `WL_HOME\samples\server\examples\src\examples`, where `WL_HOME` is the top-level directory of your WebLogic Server installation. Start the examples server and obtain information about the samples and how to run them from the WebLogic Server Start menu.

## Additional JMS Examples Available for Download

Additional API examples are available for download at the [Oracle Technology Network](#). These examples are distributed as .zip files that you unzip into an existing WebLogic Server samples directory structure. You build and run the downloadable examples in the same manner as you would an installed WebLogic Server example.

## New and Changed Features in This Release

For a comprehensive listing of the new WebLogic Server features introduced in this release, see “What’s New in WebLogic Server” in *Release Notes*.

## Introduction and Roadmap

# Understanding the Messaging Bridge

The following sections describe WebLogic Messaging Bridge concepts and functionality:

- [“What Is a Messaging Bridge?” on page 2-1](#)
- [“Messaging Bridge Components” on page 2-2](#)
- [“Configuring and Managing a Messaging Bridge” on page 2-6](#)


## What Is a Messaging Bridge?

The WebLogic Messaging Bridge is a forwarding mechanism that provides interoperability between WebLogic JMS implementations, and between JMS and other messaging products. Use the Messaging Bridge to integrate your messaging applications between:

- Any two implementations of WebLogic JMS, including those from separate releases of WebLogic Server.
- WebLogic JMS implementations that reside in separate WebLogic domains.
- WebLogic JMS and a third-party JMS product (for example, MQSeries).

A messaging bridge instance forwards messages between a pair of bridge source and target destinations. These destinations are mapped to a pair of bridge source and target destinations. The messaging bridge reads messages from the source bridge destination and forwards those messages to the target bridge destination. For WebLogic JMS and third-party JMS products, a messaging bridge communicates with source and target destinations using the Java EE Connector Architecture (JCA) resource adapters provided with WebLogic Server. See [Figure 2-1](#).

Figure 2-1 WebLogic Messaging Bridge



You designate source and target bridge destinations as either [queues](#), [topics](#), or [distributed destinations](#). Optionally, specify a quality of service (QOS), as well as message filters, transaction semantics, and connection retry policies. Once you configure a messaging bridge you can perform management tasks easily from the Administration Console, including suspending bridge traffic temporarily whenever necessary and monitoring the status of all your configured bridges.

## Messaging Bridge Components

The following sections describe resources you need to use a messaging bridge:

- [“Resource Adapters” on page 2-2](#)
- [“Source and Target Bridge Destinations” on page 2-6](#)
- [“Messaging Bridge Instance” on page 2-6](#)

## Resource Adapters

A messaging bridge uses JCA resource adapters to communicate with the configured source and target JMS destinations. You need to associate both the source and target JMS destinations with

a *supported* resource adapter in order for the bridge to communicate with them. The JNDI name for the adapter is configured as part of the resource adapter's deployment descriptor. See [Table 2-1](#).

Resource adapters for different types of JMS destinations are provided in exploded format or in a `.rar` file. The exploded format gives you an easy way to modify resource adapter deployment descriptor parameters, such as the `max-capacity` of the connection factory that specifies the maximum number of connections available for bridge instances.

**Note:** Changing a deployment descriptor for a resource adapter using the exploded format does not update the descriptor packaged in the `.rar` file. See [“Setting the Number of Connection Factories” on page 3-4](#).

## Understanding the Messaging Bridge

The supported resource adapters are located in the `WL_HOME\server\lib` directory and are described in the following table.

**Table 2-1 Messaging Bridge Resource Adapters and JNDI Names**

Adapter	JNDI Name	Description
jms-xa-adp	eis.jms.WLSConnectionFactoryJNDIXA	<p>Provides transaction semantics via the XAResource. Used when the required QOS is <i>Exactly-once</i>. This envelops a received message and sends it within a user transaction (XA/JTA). The following requirements apply to use of this resource adapter:</p> <ul style="list-style-type: none"> <li>• Any WebLogic Server implementation being bridged must be release 7.0 or later.</li> <li>• The source and target JMS connection factories must be configured to use the XAConnectionFactory.</li> </ul> <p><b>Note:</b> Before deploying this resource adapter, refer to the <a href="#">“Configuring Interoperability for WebLogic Domains”</a> on page 4-2 for specific transactional configuration requirements and guidelines.</p>
jms-notran-adp	eis.jms.WLSConnectionFactoryJNDINoTX	<p>Provides no transaction semantics. Used when the required QOS is <i>Atmost-once or Duplicate-okay</i>. If the requested QOS is <i>Atmost-once</i>, the resource adapter uses AUTO_ACKNOWLEDGE mode. If the requested QOS is <i>Duplicate-okay</i>, CLIENT_ACKNOWLEDGE is used.</p> <p><b>Note:</b> For more information about the acknowledge modes used in non-transacted sessions, see <a href="#">“Understanding WebLogic JMS”</a> in <i>Programming WebLogic JMS</i>.</p>

## Source and Target Bridge Destinations

A messaging bridge connects two actual destinations that are mapped to bridge destinations: a source destination *from which* messages are received, and a target destination *to which* messages are sent. For JMS messaging products, whether it is a WebLogic JMS implementation or a third-party JMS provider, you need to configure a JMS bridge destination instance for each actual source and target JMS destination being mapped to a messaging bridge. A JMS bridge destination instance defines a unique name for a bridge's source and target destinations within a WebLogic domain; the name of the adapter used to communicate with the specified destination; property information to pass to the adapter (such as Connection URL and Connection Factory JNDI Name), and, optionally, a user name and password. See [“Create JMS bridge destinations”](#) in *Administration Console Online Help*. See:

- [“Interoperating with Different WebLogic Server Releases”](#) on page 4-1 or [“Interoperating with Foreign Providers”](#) on page 4-3 sections for specific configuration requirements and guidelines.
- When configuring third-party JMS provider bridge destination, use the Foreign JMS Server feature to configure multiple source or target destinations quickly. See [Simplified Access to Remote or Foreign JMS Providers](#) in *Programming WebLogic JMS*.

## Messaging Bridge Instance

A messaging bridge instance communicates with the configured source and target bridge destinations. For each mapping of a source destination to a target destination, whether it is another WebLogic JMS implementation or a third-party JMS provider, you must configure a messaging bridge instance. Each messaging bridge instance defines the source and target destination for the mapping, a message filtering selector, a QOS, transaction semantics, and various reconnection parameters. See [“Create Messaging Bridge Instances”](#) in *Administration Console Online Help*.

## Configuring and Managing a Messaging Bridge

The following sections provide information on how to use the Administration Console to configure and manage a messaging bridge:

- [“Create a Messaging Bridge Instance”](#) on page 2-7
- [“Manage a Messaging Bridge Instance”](#) on page 2-7



## Create a Messaging Bridge Instance

Creating a messaging bridge consists of the following tasks:

1. Create source and target bridge destinations.
2. Deploy a resource adapter.
3. Create a messaging bridge instance.
4. Target the messaging bridge.

The Administration Console assists you in creating a messaging bridge by deploying an appropriate resource adapter and setting the values of some attributes. You may need to change messaging bridge settings to better suit your environment. See [“Create Messaging Bridge Instances”](#) in *Administration Console Online Help*.

## Manage a Messaging Bridge Instance

Typical tasks required to manage a messaging bridge using the Administration Console include:

- Monitoring the status of all configured messaging bridges in your domain. See [“Monitor messaging bridges”](#) in the *Administration Console Online Help*.
- Suspending and restarting an active messaging bridge. See [“Suspend and restart messaging bridges”](#) in the *Administration Console Online Help*.
- Configuring the default execute thread pool size for your messaging bridges. See [“Configure messaging bridge execute thread pool size”](#) in the *Administration Console Online Help*.
- Deploying a resource adapter. See [“Deploy resource adapters”](#) in the *Administration Console Online Help*.
- Creating a trusted security relationship. See [“Configuring Domains for Inter-Domain Transactions”](#) in *Programming WebLogic JTA*.

## Understanding the Messaging Bridge

# Designing a Messaging Bridge

Use the following information to help you design and configure a WebLogic Messaging Bridge:

- [“When to use a Messaging Bridge” on page 3-1](#)
- [“When to Avoid using a Messaging Bridge” on page 3-2](#)
- [“Selecting a Quality-of-Service \(QOS\) Level” on page 3-3](#)
- [“Messaging Persistence” on page 3-4](#)
- [“Message Ordering” on page 3-4](#)
- [“Setting the Number of Connection Factories” on page 3-4](#)
- [“Preserving Message Properties” on page 3-5](#)
- [“Using the JMSXUserID Property with a Messaging Bridge” on page 3-6](#)
- [“Using Distributed Destinations as Source and Target Destinations” on page 3-6](#)
- [“Tuning a WebLogic Messaging Bridge” on page 3-7](#)

## When to use a Messaging Bridge

The following sections provide information on when to use a messaging bridge:

- [“Store and Forward Messaging” on page 3-2](#)
- [“Replicating a Topic” on page 3-2](#)

## Store and Forward Messaging

A messaging bridge provides high availability for remote destinations. Store and forward messaging enables a local client to produce to a local destination and have those messages automatically forwarded to the remote destination when it is available. This allows a local client to continue to produce messages when a remote destination is not available. See [“Messaging Persistence” on page 3-4](#).

Use the WebLogic Messaging Bridge to provide an administrative solution to store and forward messages between:

- Any two implementations of WebLogic JMS, including those from separate releases of WebLogic Server.
- WebLogic JMS implementations that reside in separate WebLogic domains.
- WebLogic JMS with a third-party JMS product (for example, MQSeries).

## Replicating a Topic

A messaging bridge can be used to replicate a topic, similar to using the [distributed topics](#) feature available in WebLogic Server releases 7.0 and higher, consequently improving scalability and high availability in some scenarios. Topic replication is accomplished by configuring the bridge to subscribe to one topic and forward the topic's messages to another topic, in essence creating two topics with the same message stream. See [“Create messaging bridge instances”](#) in *Administration Console Online Help*.

## When to Avoid using a Messaging Bridge

The following sections provide information on when to avoid using messaging bridge:

- Receiving messages from a remote destination—Use a message driven EJB or implement a client consumer directly.
- Sending messages to a local destination—Send directly to the local destination.
- Environment with low tolerance for message latency. Messaging Bridges increase latency and may lower throughput. Messaging bridges increase latency for messages as they introduce an extra destination in the message path and may lower throughput because they forward messages using a single thread.

- Forward messages between WebLogic 9.0 and higher domains—Use WebLogic Store-and-Forward.

The following table summarizes information on when to use WebLogic Messaging Bridge or other forwarding technologies:

**Table 3-1 Comparing Message Forwarding Technologies**

Feature	Messaging Bridge	Message Driven Beans	WebLogic Store-and-Forward
Implementation mechanism	Administrative	Programmatic	Administrative
Support for foreign and legacy providers	Yes	No	No, use to forward messages between WebLogic 9.0 and higher domains.

## Selecting a Quality-of-Service (QOS) Level

The WebLogic Messaging Bridge supports three different QOS levels:

- Exactly-once—The highest QOS guarantees that a message is sent to the remote endpoint once and only once. With Exactly-once, messages survive server crashes and network down time, while guaranteeing one occurrence of each message at the endpoint.
- At-least-once—Guarantees that a message is sent to the remote endpoint, but with the possibility of duplicates. With At-least-once, multiple copies of a message might show up on the remote endpoint because of network failures or server crashes that occur when the message is in transit.
- At-most-once—The lowest QOS guarantees that each message is sent to the remote endpoint only once, if at all. It does not guarantee that a message is sent to the endpoint. With At-most-once, messages may get lost because of network failures or server crashes. No duplicate messages will reach the endpoint.

In some instances, the target destination may not be able to provide the quality of service configured for the bridge. In these cases, configure the bridge instance to allow the quality of service to be degraded by setting the `QOSDegradationAllowed` flag. See [“Create messaging bridge instances”](#) in *Administration Console Online Help*.

## Messaging Persistence

Store-and-forward messaging enables a local JMS client to produce messages to a local destination and have those messages automatically forwarded to a remote destination when it is available. The bridge will forward these messages to the target destination when it is restarted. A messaging bridge will store-and-forward messages to a target destination under the following conditions:

- The source destination is a queue.
- The source destination is a topic *and* the [Durability Enabled](#) attribute is set. This creates a durable subscription. For more information configuring durable topic subscribers, see [“Setting Up Durable Subscriptions”](#) in *Programming WebLogic JMS*.

## Message Ordering

If an application message is in a transaction, saving the message in the persistent store must be part of the user transaction to preserve exactly-once semantics. In particular, the message is removed from the persistent store as part of the transaction rollback if the application decides to rollback the transaction. However, forwarding is *not* part of the application transaction. The sending agent does not forward a transactional message until the transaction commits. Within a transaction, message ordering is preserved based on when the messages are sent.

To ensure message ordering, configure a message unit-of-order. See [“Using Message Unit-of-Order”](#) in *Programming WebLogic JMS*.

## Setting the Number of Connection Factories

You may need to modify the capacity of the connection factory associated with each resource adaptor by adjusting the `initial-capacity` and `max-capacity` attributes the `weblogic-ra.xml` descriptor file. In general, the value of the `max-capacity` attribute should be at least two times the number of bridge instances. For example:

The default configuration sets the value of the `max-capacity` attribute to 20. This setting is adequate for environments that have up to ten message bridge instances targeted. If you increase the number of bridge instances to 15, increase the `max-capacity` attribute to 30.

Use the following steps to modify the `weblogic-ra.xml` descriptor file:

1. Using the editor of your choice, update the attribute with the desired value. See [Listing 3-1](#).
2. Deploy the updated adapter.

3. Stop and restart any bridge instance that requires the new values.

### Listing 3-1 Example `weblogic-ra.xml` Descriptor File

---

```
<weblogic-connection-factory-dd>

    <connection-factory-name>WLSJMSConnectionFactoryLocal</connection-factory-name>

    <jndi-name>eis/jms/WLSConnectionFactoryJNDILocal</jndi-name>

    <pool-params>
        <initial-capacity>0</initial-capacity>
        <max-capacity>20</max-capacity>
    </pool-params>

</weblogic-connection-factory-dd>
```

---

## Preserving Message Properties

Set `PreserveMsgProperty` to preserve message properties in a message header when a message is forwarded by a bridge instance. In previous releases, message properties are inherited from the `Default Delivery Mode` attribute on the connection factory used when a message is forwarded to its target destination. If the `Default Delivery Mode` is persistent, a non-persistent message is forwarded as a persistent message resulting in a significant performance loss.

When `PreserveMsgProperty` is enabled, an incoming non-persistent message is forwarded by the bridge to the target destination as a non-persistent message and an incoming persistent message is forwarded to the target destination as a persistent message. See “[Configure messaging bridge instances](#)” in *Administration Console Online Help*.

The behavior of a messaging bridge instance is determined according to the following guidelines:

- The `PreserveMsgProperty` is not enabled. This setting provides the same forwarding behavior as previous releases.

- The default value of `PreserveMsgProperty` when configuring a messaging bridge instance is not enabled.
- The `PreserveMsgProperty` is enabled. Message properties are preserved as described the following table:

**Table 3-2 Message Properties Preserved at Target Destination by WebLogic Server Release**

Property	WebLogic Server 9.0 and Higher	WebLogic Server 8.1, 7.0	Foreign JMS Servers
Message ID	Yes	No	No
Timestamp	Yes	No	No
User ID	Yes	No	No
Delivery Mode	Yes	Yes	Yes
Priority	Yes	Yes	Yes
Expiration Time	Yes	Yes	Yes
Redelivery Limit	Yes	No	No
Unit-of-Order name	Yes	No	No

## Using the `JMSXUserID` Property with a Messaging Bridge

The messaging bridge does not disclose a message's `JMSXUserID` across messaging bridge boundaries. A `JMSXUserID` is a system generated property that identifies the user sending the message, see the [JMS Specification](#).

## Using Distributed Destinations as Source and Target Destinations

A messaging bridge can send to and receive from [distributed destinations](#). Oracle recommends the following configurations:

- If the source is a distributed destination, the bridge is pinned to one of the members when it connects to the destination. It stays connected to that member until an event occurs that breaks the connection. On reconnection, the bridge uses the next available member. Once a



bridge is connected, it does not receive messages from other members of the distributed destination. It is a best practice to configure one bridge for each member of a distributed destination using the member's JNDI Name.

- If the target is a distributed destination, the best practice is to send to the distributed destination using the distributed destination's JNDI Name and disable server affinity. This allows the distributed destination to load balance incoming messages. See [“Load Balancing for JMS”](#) in *Using WebLogic Server Clusters*.

## Tuning a WebLogic Messaging Bridge

The main objective when tuning a messaging bridge is to improve overall messaging performance. Raw speed, though important, is only one of several performance-related factors. Other performance factors include reliability, scalability, manageability, monitoring, user transactions, message-driven bean support, and integration with an application server. See [“Tuning WebLogic Message Bridge”](#) in *WebLogic Server Performance and Tuning*:

## Designing a Messaging Bridge

# Interoperating with Different WebLogic Server Releases or Foreign Providers

The following sections provide interoperability guidelines for using the WebLogic Messaging Bridge to access JMS destinations on different releases of WebLogic Server or when accessing foreign providers:

- [“Interoperating with Different WebLogic Server Releases”](#) on page 4-1
- [“Interoperating with Foreign Providers”](#) on page 4-3

## Interoperating with Different WebLogic Server Releases

The following interoperability guidelines apply when using the messaging bridge to access JMS destinations on different releases of WebLogic Server and in other WebLogic Server domains.

- [“Naming Guidelines for WebLogic Servers and Domains”](#) on page 4-1
- [“Configuring Interoperability for WebLogic Domains”](#) on page 4-2

**Note:** When the messaging bridge is used to communicate between two domains running different releases of WebLogic Server, Oracle recommends that the messaging bridge be configured to run on the domain using the latest release of WebLogic Server.

## Naming Guidelines for WebLogic Servers and Domains

Unique naming rules apply to all WebLogic Server deployments if more than one domain is involved. Therefore, make sure that:

- WebLogic Server instances and domain names are unique.

- WebLogic JMS server names are unique name across domains.
- If a JMS file store is being used for persistent messages, the JMS file store name must be unique across domains.

## Configuring Interoperability for WebLogic Domains

Configuring interoperability between domains depends on the QOS:

- [“Configuring Interoperability for Exactly-once QOS”](#) on page 4-2
- [“Configuring At-least-once or At-most-once QOS”](#) on page 4-3

### Configuring Interoperability for Exactly-once QOS

Use the following guidelines to configure interoperability when a bridge running on a release 7.0 or higher domain must handle transactional messages (using the Exactly-once QOS) between two release 7.0 or later domains

- You must correctly configure either Cross Domain Security or Security Interop Mode for all participating domains.  
  
Keep all the domains used by your process symmetric with respect to Cross Domain Security configuration and Security Interop Mode. Because both settings are set at the domain level, it is possible for a domain to be in a mixed mode, meaning the domain has both Cross Domain Security and Security Interop Mode set. For more information, see:
  - [Configuring Domains for Inter-Domain Transactions](#) in *Programming WebLogic JTA*
  - [Changing the Asynchronous Mode Enabled Attribute](#) in *WebLogic Server Performance and Tuning*.
- If a JMS file store is being used for persistent messages, the JMS file store name must be unique across WebLogic domains, as described in [“Naming Guidelines for WebLogic Servers and Domains”](#) on page 4-1.
- Make sure that the XA connection factory is enabled for the domains by selecting the XAConnection Factory Enabled check box. See [“Configure connection factory transaction parameters”](#) in *Administration Console Online Help*.
- Deploy the transaction resource adapter, `jms-xa-adj.rar`, on the domain where the messaging bridge is running, as described in [“Deploy resource adapters”](#) in *Administration Console Online Help*.

- When configuring the JMS bridge destinations, as described in [“Create JMS bridge destinations”](#) in *Administration Console Online Help*, do the following for both the source and target destinations:
  - In the Adapter JNDI Name field, identify the transaction adapter’s JNDI name, `eis.jms.WLSConnectionFactoryJNDIXA`.
  - Do not enter anything in the Adapter Classpath field.
- Select a Quality Of Service of *Exactly-once*, as described in [“Configure messaging bridge instances”](#) in *Administration Console Online Help*.

## Configuring At-least-once or At-most-once QOS

There are no special security configuration requirements for the bridge to interoperate between two releases of 7.0 or later domains. However, if you wish to provide more secure communication between domains, you can configure Cross Domain Security.

**Note:** Keep all the domains used by your process symmetric with respect to Cross Domain Security configuration—all domains use Cross Domain Security (or are on the appropriate exception lists) or none of the domains have Cross Domain Security configured. For more information, see:

- [Configuring Configuring Security for a WebLogic Domain](#) in *Securing WebLogic Server*
- [Changing the Asynchronous Mode Enabled Attribute](#) in *WebLogic Server Performance and Tuning*.

# Interoperating with Foreign Providers

When configuring a messaging bridge involves interoperability with a third-party messaging provider, you must configure the following:

- Before starting WebLogic Server:
  - Supply the provider’s CLASSPATH in the WebLogic Server CLASSPATH.
  - Include the PATH of any native code required by the provider’s client-side libraries in the WebLogic Server system PATH. (This variable may vary depending on your operating system.)
- In the `JMSBridgeDestination` instance for the third-party messaging product being bridged, provide *vendor-specific* information in the following attributes:
  - Connection URL

- Initial Context Factory
- Connection Factory JNDI Name
- Destination JNDI Name

**Note:** The messaging bridge cannot provide the “Exactly-once” quality of service when the source and target bridge destinations are located on the same resource manager (that is, when the bridge is forwarding a global transaction that is using the XA resource of the resource manager). For example, when using MQ Series, it is not possible to use the same Queue Manager for the source and target bridge destinations.

For more information on configuring the remaining attributes for a JMS Bridge Destination, see [“Create JMS Bridge destinations”](#) in *Administration Console Online Help*.

# FAQs: WebLogic Messaging Bridge

The following section provides answers to frequently asked questions (FAQs) for the WebLogic Messaging Bridge:

- [“Why did the messaging bridge fail to connect to the source bridge destination?” on page 5-2](#)
- [“Can the messaging bridge handle two-phase or global transactions between separate WebLogic Server domains or between different releases?” on page 5-2](#)
- [“I configured the messaging bridge to use the Exactly-once quality of service for two-phase transactions. So why am I getting a “quality of service is unreachable” error?” on page 5-3](#)
- [“Can a messaging bridge to automatically downgrade the quality of service if the Exactly-once service isn’t available on either the source or target bridge destination?” on page 5-3](#)
- [“I deployed the transactional jms-xa-adp.rar resource adapter on domain where the message bridge is running, but I still get a “failed to find bridge adapter” message?” on page 5-4](#)
- [“When configuring a source or target messaging bridge destination, do I need to set the Adapter Classpath field?” on page 5-4](#)
- [“How do I enable debugging for the messaging bridge?” on page 5-4](#)
- [“What do the messaging bridge monitoring states indicate on the Monitor Messaging Bridge console page?” on page 5-5](#)

- [“Is there another way to monitor the messaging bridge without using the Administration Console?” on page 5-6](#)
- [“Can the messaging bridge use distributed destinations as source and target destinations?” on page 5-6](#)

## Why did the messaging bridge fail to connect to the source bridge destination?

Either an error occurred when configuring the source bridge destination parameters, or the actual source destination is not running and cannot communicate with the messaging bridge.

- Verify whether the bridge’s source destination is correctly configured, by making sure that the following fields on the **JMS Bridge Destination Æ Configuration** console page have been properly completed:
  - **Connection URL**—this must be the URL of the JNDI provider used to look up the connection factory and actual destination.
  - **Destination JNDI Name**—this must be the JNDI name of the actual destination mapped to the source bridge destination.
  - **Connection Factory JNDI Name**—this must be the connection factory used to create a connection for the actual destination mapped to the source bridge destination.
  - **User Name/Password**—make sure that this user ID has permission to access the actual source destination.
- Verify that the actual source queue or topic destination mapped to the source bridge destination is running and healthy, as follows:
  - Is the WebLogic Server instance hosting the source destination running?
  - Is the JMS server hosting the source destination correctly deployed?

**Note:** This troubleshooting scenario for correcting a source bridge destination connection failure also applies to target bridge destinations.

## Can the messaging bridge handle two-phase or global transactions between separate WebLogic Server domains or between different releases?

Yes, see [“Interoperating with Different WebLogic Server Releases” on page 4-1](#).



## **I configured the messaging bridge to use the Exactly-once quality of service for two-phase transactions. So why am I getting a “quality of service is unreachable” error?**

There are some additional configuration requirements for the messaging bridge to handle transactions between WebLogic domains:

- The supported adapters are located in the `WL_HOME\server\lib` directory. For the Exactly-once QOS, the transaction adapter, `jms-xa-adj.rar`, must be deployed in the domain where the bridge is running, via the select Deployments Æ Connector node on the console.
- This `jms-xa-adj.rar` adapter must also be identified in the Adapter JNDI Name attribute as `eis.jms.WLSConnectionFactoryJNDIXA` on the JMS Bridge Destination Æ Configuration tab for both the source and target bridge destinations.
- For WebLogic JMS, verify that you are using the transactional `XAConnectionFactory` for the queue or topic destinations mapped to both the source and target bridge destinations. To verify this, the following attributes must be set on the JMS Æ Connection Factory Æ Configuration Æ Transactions console tab or in the configuration file (`config.xml`):
  - `UserTransactionsEnabled=true`
  - `XAConnectionFactory=true`
- For third-party JMS vendors, verify that you are using a transactional connection factory for the destinations mapped to the source and target bridge destinations.

For more information about using the Exactly-once QOS when interoperating between releases, see [“Interoperating with Different WebLogic Server Releases” on page 4-1](#).

## **Can a messaging bridge to automatically downgrade the quality of service if the Exactly-once service isn’t available on either the source or target bridge destination?**

Yes, just make sure to select the `QOS Degradation Allowed` check box on the Messaging Bridge Æ Configuration Æ General administration console page.

## **I deployed the transactional `jms-xa-adp.rar` resource adapter on domain where the message bridge is running, but I still get a “failed to find bridge adapter” message?**

You need to associate both the source and target bridge destinations with the appropriate `.rar` adapters in order for the bridge to communicate with them. For the `jms-xa-adp.rar` transaction adapter, it must be identified in the Adapter JNDI Name attribute as `eis.jms.WLSConnectionFactoryJNDIXA` on the JMS Bridge Destination  $\text{\AE}$  Configuration tab for both the source and target bridge destinations.

**Note:** The “failed to find bridge adapter” message does not necessarily indicate a problem if it only occurs once. However, if it occurs repeatedly, you should check the adapter deployment and the adapter JNDI name used in the source and target bridge destinations.

For more information about the bridge resource adapters, see [“Resource Adapters” on page 2-2](#).

## **When configuring a source or target messaging bridge destination, do I need to set the Adapter Classpath field?**

Leave the Adapter Classpath field blank when connecting to source and target destinations that are both running in WebLogic Server instances. When connecting to a third-party JMS provider, the bridge destination must supply the provider’s `CLASSPATH` in the WebLogic Server `CLASSPATH`.

## **How do I enable debugging for the messaging bridge?**

You can enable debugging for the messaging bridge using either of the following methods:

- Add the following lines to your WebLogic start script (before the `weblogic.Server` line):

```
-Dweblogic.debug.DebugMessagingBridgeStartup=true  
-Dweblogic.debug.DebugMessagingBridgeRuntime=true
```

- Add the following statements to the `ServerDebug` entry in your configuration file (`config.xml`) for the server that the messaging bridge is running on:

```
DebugMessagingBridgeStartup="true"  
DebugMessagingBridgeRuntime="true"
```

Once debugging is enabled for the messaging bridge, the debugging messages are sent to the server log by default. However, if you want them to appear in the Administration Console, add `“DumpToConsole”` to the statements shown above. For example:

-Dweblogic.debug.DebugMessagingBridgeStartupDumpToConsole=true

## What do the messaging bridge monitoring states indicate on the Monitor Messaging Bridge console page?

When monitoring a messaging bridge's state, use the following table to determine a course of action, if necessary. For more information, see [“Manage a Messaging Bridge Instance” on page 2-7](#).

**Table 5-1 Messaging Bridge Monitoring States**

Description	Action
WARN: Failed to find the source adapter	Check if the adapter is deployed or the JNDI name in the source JMSBridgeDestination instance is correct.
WARN: Failed to find the target adapter	Check if the adapter is deployed or the JNDI name in the target JMSBridgeDestination instance is correct.
Found both of the adapters and making connections	NA
WARN: Stopped by the administrator	NA
WARN: Failed to look up the source adapter	Check if the adapter is deployed or the JNDI name in the source JMSBridgeDestination instance is correct.
WARN: Failed to look up the target adapter	Check if the adapter is deployed or the JNDI name in the target JMSBridgeDestination instance is correct.
Found two adapters and about to make connections	NA
WARN: Failed to connect to the source	<ul style="list-style-type: none"><li>• Check all the parameters configured for the source bridge destination.</li><li>• Check if the source server is running and whether the actual destination is active.</li></ul>
Connected to the source	NA
WARN: Failed to connect to the target	<ul style="list-style-type: none"><li>• Check all the parameters configured for the target bridge destination.</li><li>• Check if the target server is running and whether the actual destination is active.</li></ul>

**Table 5-1 Messaging Bridge Monitoring States**

Connected to the target	NA
Forwarding messages	NA
WARN: Failed to connect and will reconnect later	Check if the source and target bridge destinations are running and healthy.

## Is there another way to monitor the messaging bridge without using the Administration Console?

Yes, there is a run-time MBean (`MessagingBridgeRuntimeMBean`) for each bridge instance. WebLogic Server run-time MBeans provide a snapshot of information about domain resources. When a particular resource in the domain (such as a messaging bridge) is instantiated, an MBean instance is created which collects information about that resource.

The `MessagingBridgeRuntimeMBean` has a `getState()` method that currently returns a `String` (“Active” or “Inactive”) and a `getDescription()` method, which returns a `String` with more detailed information. The name of a bridge runtime MBean consists of the WebLogic Server instance name and the bridge name. If a bridge named *mybridge*, runs on WebLogic Server instance named *myserver*, the bridge runtime MBean will be named *myserver.bridge.mybridge*.

For more information, see:

- [Developing Custom Management Utilities with JMX](#).
- [Using the WebLogic Scripting Tool](#) in *WebLogic Scripting Tool*

## Can the messaging bridge use distributed destinations as source and target destinations?

Yes, the messaging bridge can send to and receive from distributed destinations. Oracle recommends the following configurations:

- If the source is distributed destination, the bridge is pinned to one of the members when it connects to the destination. It stays connected only to that member until it reconnects. This means that the bridge will not receive messages from the other members of the distributed destination. Therefore, the best practice is to configure one bridge for each member of a distributed destinations using the member's JNDIName.

- If the target is a distributed destination, the best practice is to send to the distributed destination using the distributed destination's JNDIName and disable server affinity. This allows the distributed destination to load balance incoming messages.

