

Oracle® Documaker

Docupresentation Installation Guide

12.7.1

Part number: F76382-01

January 2023

Copyright © 2009, 2020, Oracle and/or its affiliates. All rights reserved.

The Programs (which include both the software and documentation) contain proprietary information; they are provided under a license agreement containing restrictions on use and disclosure and are also protected by copyright, patent, and other intellectual and industrial property laws. Reverse engineering, disassembly, or decompilation of the Programs, except to the extent required to obtain interoperability with other independently created software or as specified by law, is prohibited.

The information contained in this document is subject to change without notice. If you find any problems in the documentation, please report them to us in writing. This document is not warranted to be error-free. Except as may be expressly permitted in your license agreement for these Programs, no part of these Programs may be reproduced or transmitted in any form or by any means, electronic or mechanical, for any purpose.

If the Programs are delivered to the United States Government or anyone licensing or using the Programs on behalf of the United States Government, the following notice is applicable:

U.S. GOVERNMENT RIGHTS

Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the Programs, including documentation and technical data, shall be subject to the licensing restrictions set forth in the applicable Oracle license agreement, and, to the extent applicable, the additional rights set forth in FAR 52.227-19, Commercial Computer Software--Restricted Rights (June 1987). Oracle USA, Inc., 500 Oracle Parkway, Redwood City, CA 94065.

The Programs are not intended for use in any nuclear, aviation, mass transit, medical, or other inherently dangerous applications. It shall be the licensee's responsibility to take all appropriate fail-safe, backup, redundancy and other measures to ensure the safe use of such applications if the Programs are used for such purposes, and we disclaim liability for any damages caused by such use of the Programs.

The Programs may provide links to Web sites and access to content, products, and services from third parties. Oracle is not responsible for the availability of, or any content provided on, third-party Web sites. You bear all risks associated with the use of such content. If you choose to purchase any products or services from a third party, the relationship is directly between you and the third party. Oracle is not responsible for: (a) the quality of third-party products or services; or (b) fulfilling any of the terms of the agreement with the third party, including delivery of products or services and warranty obligations related to purchased products or services. Oracle is not responsible for any loss or damage of any sort that you may incur from dealing with any third party.

Oracle, JD Edwards, and PeopleSoft are registered trademarks of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners.

CONTENTS

Preface	4
Audience	4
Documentation Accessibility	4
Related Documents	6
Conventions	6
Installing Docupresentment on UNIX	7
Overview	8
Downloading the Software	10
Using the Oracle Software Delivery Cloud	10
Installing a New System	12
Scenario 1: New Installation of Version 12.6.3	13
Installing Docupresentment 12.6.3 RTE	13
Installing the Documaker Bridge Shared Objects RTE	15
Scenario 2: Upgrading From a Version 1.x Environment (overlay)	16
Installing the Docupresentment 12.6.3 RTE	16
Scenario 3: Upgrading from Version 2.4 to Version 12.6.3	20
Installing the Docupresentment 12.6.3 RTE	20
Scenario 4: Modified Upgrade from Version 1.x	24
Installing Docupresentment 12.6.3 RTE	24
Installing Documaker Bridge Shared Objects	26
Testing Your System	26
Customizing Your Docupresentment 12.6.3 Environment	27
Scenario 5: Modified Upgrade from Version 2.x	28
Installing Docupresentment 12.6.3 RTE	28
Installing Documaker Bridge Shared Objects	30
Testing Your System	30
Customizing Your Docupresentment 12.6.3 Environment	31
Scenario 6: Patch Upgrade of a Version 12.6.3 Environment	32
Testing the Installation	33
Uninstalling the System	37
Installing Docupresentment on Windows	38
Overview	39
Downloading the Software	40
Using the Oracle Software Delivery Cloud	40
Installing the Docupresentment Server	42
Installing Shared Objects	46
Installing the Docupresentment Client	48
Selecting a queuing Method	50
Testing Your Installation	56
Setting Up the System as a Service	59
Verifying Docupresentment was Installed as a Service	60
Uninstalling Docupresentment as a Service	62
Uninstalling the System	63
Troubleshooting the Client	64
Installing the Docupresentment with a Response File	66

Preface

Oracle has Internet solutions for managing your documents. Docupresentment helps manage the flow of your documents. Docupresentment lets you access your documents with a web browser from your intranet or the Internet. The standard web browser interface includes security features, document database lookup, and document viewing in PDF format using the Adobe Acrobat Reader.

AUDIENCE

This document is designed for system supervisors and is intended to help you install and set up Oracle Documaker's Docupresentment (previously known as Internet Document Server).

DOCUMENTATION ACCESSIBILITY

Accessibility of Links to External Websites in Documentation

This documentation may contain links to websites of other companies or organizations that Oracle does not own or control. Oracle neither evaluates nor makes any representations regarding the accessibility of these websites.

Oracle Support

If you have any questions about the installation or use of our products, please call +1.800.223.1711 or visit the My Oracle Support website:

<http://www.oracle.com/us/support/index.html>

Go to My Oracle Support to find answers in the Oracle Support Knowledge Base, submit, update or review your Service Requests, engage the My Oracle Support Community, download software updates, and tap into Oracle proactive support tools and best practices.

Hearing impaired customers in the U.S. who need to speak with an Oracle Support representative may use a telecommunications relay service (TRS); information about TRS is available at <http://www.fcc.gov/cgb/consumerfacts/trs.html>, and a list of phone numbers is available at <http://www.fcc.gov/cgb/dro/trsphonebk.html>. International hearing impaired customers should use the TRS at 1.605.224.1837.

Contact

USA:+1.800.223.1711

Canada: 1.800.668.8921 or +1.905.890.6690

Latin America: 877.767.2253

For other regions including Latin America, Europe, Middle East, Africa, and Asia Pacific regions: Visit- <http://www.oracle.com/us/support/contact/index.html>

Copyright ©2015 Oracle and/or its affiliates. All rights reserved.

Follow us

 <https://blogs.oracle.com/insurance>

 <https://www.facebook.com/oraclefs>

 <https://twitter.com/oraclefs>

 <https://www.linkedin.com/groups?gid=2271161>

RELATED DOCUMENTS

For more information, refer to the following Oracle resources:

- Documaker Administration Guide
- Output Management Guide
- Docupresentation SDK Reference

CONVENTIONS

The following text conventions are used in this document:

Convention	Description
bold	Indicates information you enter.
<i>italic</i>	Italic type indicates book titles, emphasis, or placeholder variables for which you supply particular values.
monospace	Monospace type indicates commands, URLs, code in examples, and text that appears on the screen.

Chapter 1

Installing Docupresentment on UNIX

This chapter provides information on installing Docupresentment on UNIX-based machines, such as those running Linux.

You will find this information:

- *Overview* on page 8
- *Downloading the Software* on page 10
- *Installing a New System* on page 12
- *Scenario 1: New Installation of Version 12.6.3* on page 13
- *Scenario 2: Upgrading From a Version 1.x Environment (overlay)* on page 16
- *Scenario 3: Upgrading from Version 2.4 to Version 12.6.3* on page 20
- *Scenario 4: Modified Upgrade from Version 1.x* on page 24
- *Scenario 5: Modified Upgrade from Version 2.x* on page 28
- *Scenario 6: Patch Upgrade of a Version 12.6.3 Environment* on page 32
- *Testing the Installation* on page 33
- *Uninstalling the System* on page 37

OVERVIEW

This topic describes how to install Docupresentation version 12.6.3 with shared objects using the default installation options. The steps in this topic tell you how to:

- Set up the basic infrastructure to support Docupresentation 12.6.3
- Install Docupresentation 12.6.3
- Make sure the system is working correctly

Docupresentation 12.6.3 is designed to work with third party applications, such as WebSphere Application Server, Apache, or Tomcat, and queuing managers such as IBM MQ. This topic does not provide installation instructions on non-Oracle products. Please consult the specific product manuals for installation and configuration instructions for your particular UNIX environment.

Docupresentation version 12.6.3 and Shared Objects - Documaker Bridge 12.6.3 (or higher) are packaged as installation scripts in the UNIX/Linux environments. Typically, the file suffix identifies the target OS of the installer. For example, a script with an extension of *lnx* is for the Linux operating system.

After you get the appropriate installation scripts, make sure the scripts have the *execute* permission on the file. The files must be installed as a *user* — not as *root*.

Hardware Test Environments

Docupresentation 12.6.3 was tested on various UNIX/Linux platforms. This table lists the configurations that have been tested.

Linux systems

Model*	Dell PWS450
CPU	2 x 12.22.40GHz Xeon processors2.5
Memory*	3GB2.52.5
Hard disk**	70GB SCSI drive

*Additional memory and a faster 2.5 CPU are not required, but will improve performance.

** Additional space required for your customized forms.

Checking the Software Requirements

Docupresentment 12.6.3 requires JRE 1.8.172 for Linux. Check the server's installed Java version by typing the following command in a terminal window:

```
java -version
```

If you see an error, check your PATH environment variable to see if Java is in your path. You can use the *which java* command to see if Java is installed.

Note Docupresentment 12.6.3 supports the 32-bit version of Java. Docupresentment 12.6.3 does not operate properly in 64-bit versions of the JRE.

Creating the Required User and Directories

Oracle recommends that you install and run Docupresentment as a *user* — not as *root*. Create the user account you will use to run Docupresentment 12.6.3.

When you execute the installation script, it prompts you for a directory location for the full installation. Typically, Docupresentment is installed in the home directory of the user you created.

DOWNLOADING THE SOFTWARE

Docupresentment is available for download via the Oracle Software Delivery Cloud website. The installation contains the server (including the SDK), bridges, and client. You can pick Documaker component version separately from Docupresentment after having the separate installations for the required components. The latest version of Documaker is version 12.6.3. Generally, you would want the latest version and patch level of the software. You will find links to the latest patch levels of previous versions of Documaker at the My Oracle Support website:

<https://support.oracle.com>

Installing the correct version of Shared Objects - Documaker Bridge is especially important if you plan to use Docupresentment to run Documaker. The installation of other bridges, such as the Documanager Bridge, is optional.

USING THE ORACLE SOFTWARE DELIVERY CLOUD

Oracle applications are available for download from the [Oracle Software Delivery Cloud](#) website. The process includes:

- Logging in and agreeing to the terms and restrictions
- Searching for the applications you want to download
- Downloading those applications

Note To download the latest patches for the Oracle software you have already installed, visit the [My Oracle Support site](#) at this web address:

<https://support.oracle.com>

To download the latest documentation, visit the Oracle Technology Network (OTN) website at this web address:

<http://www.oracle.com/technetwork/>

Before you begin

The [Oracle Software Delivery Cloud](#) site lets you download versions of Oracle applications. Files on the Oracle Software Delivery Cloud are available in ZIP format. Once you download the files you need, extract the files in the ZIP file to proceed with the software installation.

Note You can download the corresponding product documentation from the Oracle Technology Network (OTN) site:

<http://www.oracle.com/technetwork/documentation/insurance-097481.html>

You will need Acrobat Reader or a similar program to view the PDF documentation. You can download Acrobat Reader at Adobe's site (www.adobe.com).

Follow these instructions to download Oracle applications:

1. First, go to the Oracle Software Delivery Cloud website:
<https://edelivery.oracle.com>
2. Sign in with your Oracle account. If you do not have an Oracle account, you can register for an account [here](#).
3. Review and accept the Terms and Restrictions.
4. Select Oracle Applications from the Product Pack list or you can search the Product.
5. Once you have selected the desired program, select the desired platform.
6. The selected products are then listed. To remove them, click the X (cross) which is adjacent to the product.
7. Once you have selected the desired product and platform, click Continue to proceed.
8. License agreement is displayed. Once you are ready to proceed, check the checkbox, then click Continue.
9. Installations are displayed. To individually download files click on the filename, to download all files click on the 'Download All' button.
10. The Oracle Software Delivery Cloud prompts you to open or save the zipped file and then starts the download.

While you can save the file on any machine you choose, we recommend you save the file onto the machine where you plan to run it. You must unzip the file on the platform for which it was intended. The length of time it takes to download an application depends on the size of the download, your connection speed, and the amount of traffic on the site.

11. Click Sign Out when you finish downloading the files you need.

INSTALLING A NEW SYSTEM

There are several installation and upgrade scenarios for Docupresentment version 12.6.3.

If you...	Follow...
Are installing Docupresentment for the first time	<i>Scenario 1: New Installation of Version 12.6.3 on page 13</i>
Have Docupresentment 1.x installed	Either: <i>Scenario 2: Upgrading From a Version 1.x Environment (overlay) on page 16</i> or <i>Scenario 4: Modified Upgrade from Version 1.x on page 24</i>
Have Docupresentment 2.4 installed and would like to upgrade to version 12.6.3	<i>Scenario 6: Patch Upgrade of a Version 12.6.3 Environment on page 32</i>
Have Docupresentment 12.6.3 installed and would like to perform a patch upgrade	<i>Scenario 6: Patch Upgrade of a Version 12.6.3 Environment on page 32</i>

Note If you are using IBM MQ (WebSphere MQ or MQ Series) or ActiveMQ for the queuing method, you must make the IBM MQ or ActiveMQ jar files available to Docupresentment. See the “Installing Third-Party Jar Files” section of the [Docupresentment Guide](#) for more information.

SCENARIO 1: NEW INSTALLATION OF VERSION 12.6.3

Installing the system for the first time involves these tasks:

- *Installing Docupresentation 12.6.3 RTE* on page 13
- *Installing the Documaker Bridge Shared Objects RTE* on page 15

INSTALLING DOCUPRESENTMENT 12.6.3 RTE

Follow these steps to install Docupresentation 12.6.3 RTE:

1. Download the Docupresentation 12.6.3 RTE and the Shared Objects - Documaker Bridge 12.6.3 installation scripts from the Oracle Software Delivery Cloud site to a directory where you have execute permissions.
2. Execute the Docupresentation 12.6.3 RTE installation script.

Enter the installation path. Either override the default installation directory location or press Enter to accept the default of `/home/userid/docupresentation`.

Note The following example screens show what you would see if you logged in as *userid* and were installing Docupresentation version 12.6.3

```
*** Docupresentation 12.6.3(Type RTE) Installation/Update ***
Loading, Please Wait ...

Please select an Installation/Update Directory:
Press <Enter> to accept default: </home/userid/docupresentation>
{y or n}?>y
```

3. Confirm the installation directory or correct it if a mistake was made when overriding the default.

```
Install Docupresentation 12.6.3(RTE) to </home/userid/docupresentation>?
{y or n}?>y

Install/Update in progress. Please wait...
Updated Base Components ...
```

4. Define the path of the 32-bit JRE directory (64 bit JRE systems will not correctly install) or accept the default detected by the installation:

```
Where is your 32-bit Java Run-time (JRE) Location?
(Example: /usr/jdk/jdk1.6.0_24/jre)
JRE Version=java version "1.8.x"
```

Setting up error email notifications

5. The installation script asks if you want to set up Watchdog error SMTP email notifications.

```
Option for WatchDog Error SMTP Email Notifications:
Do you want to configure this option now?
(Note: You can manually configure it later in the log4j logconf.xml file)
{y or n}?>
```

6. If you enter yes, the SMTP setup prompts appear:

```
SMTP Server ?>
SMTP User Account ?>
SMTP Password ?>
Send emails FROM user ?>
Send emails TO user(s)
(Note: Can be a semicolon delimited list of email addresses)
?>
Send emails CC user(s)
(Note: Can be a semicolon delimited list of email addresses)
?>
Send emails to BCC user(s)
(Note: Can be a semicolon delimited list of email addresses)
?>
```

Make the appropriate entries, as described in this table:

For this prompt	Enter...
SMTP Server	Enter the name of the SMTP server.
SMTP User Account	Enter the user ID for the SMTP account.
SMTP Password	Enter the password for the user ID you set up as the SMTP User Account.
Send emails FROM user	Enter the email address from which the email will be sent.
Send emails TO user(s)	Enter the email addresses of the recipients you want to receive emails. Separate the email addresses with semicolons.
Send emails CC user(s)	Enter the email addresses of the recipients you want to receive courtesy copies (CC) of the emails. Separate the email addresses with semicolons.
Send emails to BCC user(s)	Enter the email addresses of the recipients you want to receive blind courtesy copies (BCC) of the emails. Separate the email addresses with semicolons.

After you answer the prompts or if you enter no to indicate you do not want to set up the error email notifications, the installation script finishes.

```
Installing Setup Files ...
Please Wait ...
New Installation Components Installed ...
RTE Installation Complete.
```

INSTALLING THE DOCUMAKER BRIDGE SHARED OBJECTS RTE

Follow these steps to install the Documaker Bridge shared objects:

1. Enter the installation path. Either override the default installation directory or press ENTER to accept the default of `</home/userid/docupresentment/docserv>`. Please note that you must enter the same path (through the.../docserv level) that was supplied during the Docupresentment 12.6.3 RTE installation. For this example, use Shared Objects - Documaker Bridge 12.6.3.

```

*** Documaker RP Shared Objects Bridge 12.6.3 Installation/Update ***
Loading, Please Wait ...

Please identify your Docupresentment Installation/Update
Directory: Note: Docupresentment directory must already exist.
Press <Enter> to accept default:
</home/userid/docupresentment/docserv>
?>

```

2. Confirm the installation directory path or correct, if necessary.

```

Install Documaker RP Shared Objects Bridge 12.6 to
</home/userid/docupresentment/docserv>?
{y or n}?>y

```

```

Installation/Update in progress. Please wait...
Updated Base Components ...

```

```

Installing Setup Files ...
Please Wait ...

```

```

New Documaker RP Shared Objects Installation Components Installed ...

```

```

Setting up docserv.xml to use jre located at </usr/java6/jre> ...

```

```

Installation Complete.

```

Docupresentment installs the base system with default HTTP queues. The system should function without additional modification.

Please see *Testing the Installation* on page 33 for instructions to test a simple request using the base Docupresentment system.

SCENARIO 2: UPGRADING FROM A VERSION 1.X ENVIRONMENT (OVERLAY)

When planning a Docupresentment 12.6.3 upgrade it is important to note the path name to the installation. If the previous version included *int024*, */home/userid/docupresentment* or some other semblance of a version number in the path, you must decide to keep the naming convention same or rename the directory to */home/userid/docupresentment* or some similar name.

Docupresentment 12.6.3 will correctly run in a directory path with a prior version name, such as */home/userid/int024* or */home/userid/docupresentment*. However, accepting this naming convention could cause confusion during future support calls, so be sure to properly report your current version, revision, and patch level during conversations with support.

If you decide to modify the installation path, such as to */home/userid/docupresentment*, you must modify the following INI files in the docserv directory to reflect the new naming convention:

- Docserv.xml (any request types that might call attachments)
- Bridge configuration INI and/or XML files (Documanager bridge configuration files such as *dmg_brs.ini*)
- Documaker Bridge and Documaker Server RPDRunRP configuration files such as *dap.ini*, *rpex1.ini*, *rpex1rpd.ini*, and RPDRunRP *fsiuser* and *fsisys* INI files)
- Any client specific INI or XML (*docclnt.ini*, *docclient.xml*, *dsi.ini*) files which reference the directory location.

INSTALLING THE DOCUPRESENTMENT 12.6.3 RTE

1. Download the Docupresentment 12.6.3 RTE and the Shared Objects - Documaker Bridge 12.6.3 installation scripts from the Oracle Software Delivery Cloud site to a directory where you have execute permissions.

Note The Shared Objects - Documaker Bridge version must match the Documaker Server system installed on the host system in both version and patch level.

2. Execute the Docupresentment 12.6.3 RTE installation script.

Enter the installation path. You must point the installation to the existing *int0xx* directory or the user-specified directory name.

```
*** Docupresentment 12.6.3(Type RTE) Installation/Update ***
Loading, Please Wait ...
```

```
Please select an Installation/Update Directory:
Press <Enter> to accept default:
</home/userid/docupresentment>
?>
```


- The system detects that a previous version of Docupresentment is resident. You must choose to back up and upgrade or quit. Oracle highly recommends that you choose option 1 for back up and upgrade. When doing so, the installation script will create a backup directory under the docserv directory.

```
Docupresentment installation </home/userid/docupresentment>
for version <1.8> already exist.

Please select a upgrade type
1 = Backup and Upgrade Installation
2 = Upgrade Installation
3 = Quit
?>1
```

- Confirm the chosen path or edit if necessary. Once correct, enter **Y** to complete the installation:

```
Install Docupresentment 12.6.3 (RTE) to
</home/userid/docupresentment>?
{y or n}?>y

Upgrade in progress. Please wait...
Updated Base Components ...
```

- Define the path of the 32-bit JRE directory (64-bit JRE systems will not correctly install) or accept the default that is detected by the installation:

```
Where is your 32-bit Java Run-time (JRE) Location?
Press <Enter> to accept default: </usr/java6/jre>
?>

JRE Version=java version "1.8.x"
Installing Setup Files ...
Please Wait ...
New Installation Components Installed ...
```

Setting up error email notifications

6. The installation script asks if you want to set up Watchdog error SMTP email notifications.

```
Option for WatchDog Error SMTP Email Notifications:
Do you want to configure this option now?
(Note: You can manually configure it later in the log4j logconf.xml file)
{y or n}?>
```

7. If you enter Yes, the SMTP setup prompts appear:

```
SMTP Server ?>
SMTP User Account ?>
SMTP Password ?>
Send emails FROM user ?>
Send emails TO user(s)
(Note: Can be a semicolon delimited list of email addresses)
?>
Send emails CC user(s)
(Note: Can be a semicolon delimited list of email addresses)
?>
Send emails to BCC user(s)
(Note: Can be a semicolon delimited list of email addresses)
?>
```

Make the appropriate entries, as described in this table:

For this prompt	Enter...
SMTP Server	Enter the name of the SMTP server.
SMTP User Account	Enter the user ID for the SMTP account.
SMTP Password	Enter the password for the user ID you set up as the SMTP User Account.
Send emails FROM user	Enter the email address from which the email will be sent.
Send emails TO user(s)	Enter the email addresses of the recipients you want to receive emails. Separate the email addresses with semicolons.
Send emails CC user(s)	Enter the email addresses of the recipients you want to receive courtesy copies (CC) of the emails. Separate the email addresses with semicolons.
Send emails to BCC user(s)	Enter the email addresses of the recipients you want to receive blind courtesy copies (BCC) of the emails. Separate the email addresses with semicolons.

After you answer the prompts or if you enter no to indicate you do not want to set up the error email notifications, the installation script finishes.

```
Installing Setup Files ...
Please Wait ...
mv: 0653-401 Cannot rename docserver.sh to docserver.sh_20080416114612:
    A file or directory in the path name does not exist.
mv: 0653-401 Cannot rename docserver_simple.sh to docserver_simple.sh_20080416114612:
    A file or directory in the path name does not exist.
New Installation Components Installed ...

RTE Installation Complete.
```

Note The errors shown in this step occur because the version 1.8 installation does not include the two version 12.6 files the system is trying to rename. You can ignore these error messages.

Docupresentment installs the base system with default HTTP queues. The system should function without additional modification.

Please see *Testing the Installation* on page 33 for instructions to test a simple request using the base Docupresentment system.

SCENARIO 3: UPGRADING FROM VERSION 2.4 TO VERSION 12.6.3

When planning a Docupresentment 12.6.3 upgrade it is important to note the path name to the installation. If the previous version included *int024*, */home/userid/docupresentment* or some other semblance of a version number in the path, you must decide to keep the naming convention same or rename the directory to */home/userid/docupresentment* or some similar name.

Docupresentment 12.6.3 will correctly run in a directory path with a prior version name, such as */home/userid/int024* or */home/userid/docupresentment*. However, accepting this naming convention could cause confusion during future support calls, so be sure to properly report your current version, revision, and patch level during conversations with support.

If you decide to modify the installation path, such as to */home/userid/docupresentment*, you must modify the following INI files in the docserv directory to reflect the new naming convention:

- Docserv.xml (any request types that might call attachments)
- Bridge configuration INI and/or XML files (Documanager bridge configuration files such as *dmg_brs.ini*)
- Documaker Bridge and Documaker Server RPDRunRP configuration files such as *dap.ini*, *rpex1.ini*, *rpex1rpd.ini*, and *RPDRunRP fsiuser.ini* and *fsisys.ini* files)
- Any client specific INI or XML (*docclnt.ini*, *docclient.xml*, *dsi.ini*) files which reference the directory location.

INSTALLING THE DOCUPRESENTMENT 12.6.3 RTE

1. Download the Docupresentment 12.6.3 RTE and the Shared Objects - Documaker Bridge 12.6.3 installation scripts from the Oracle Software Delivery Cloud site to a directory where you have execute permissions.

Note The Documaker Bridge Shared Objects version should match the Documaker Server system installed on the host system in both version and patch level.

2. Execute the Docupresentment 12.6.3 RTE installation script.

Enter the installation path. You must point the installation to the existing *int0xx* directory or the user-specified directory name.

```

*** Docupresentment 12.6.3 (Type RTE) Installation/Update ***
Loading, Please Wait ...

Please select an Installation/Update Directory:
Press <Enter> to accept default: </home/userid/docupresentment>
?>

```

3. The system detects that a previous version of Docupresentment is resident. You must choose to back up and upgrade, or quit. Oracle highly recommends that you choose option 1 for back up and upgrade. When doing so, the installation script will create a backup directory under the docserv directory.

```
Docupresentment installation </home/userid/docupresentment> for version <2.2> already exist.

Please select a upgrade type
 1 = Backup and Upgrade Installation
 2 = Upgrade Installation
 3 = Quit
?>2
```

4. Confirm the chosen path or edit if necessary. Once correct, enter **Y** to complete the installation:

```
Install Docupresentment 12.6.3 (RTE) to </home/userid/docupresentment>?
{y or n}?>y

Upgrade in progress. Please wait...
Updated Base Components...
```

5. Define the path of the 32-bit JRE directory (64-bit JRE systems will not correctly install) or accept the default that is detected by the installation:

```
Where is your 32-bit Java Run-time (JRE) Location?
Press <Enter> to accept default: </usr/java6/jre>
?>/usr/java6/jre
JRE Version=java version "1.8.x"
```

Setting up error email notifications

6. The installation script asks if you want to set up Watchdog error SMTP email notifications.

```
Option for WatchDog Error SMTP Email Notifications:
Do you want to configure this option now?
(Note: You can manually configure it later in the log4j logconf.xml file)
{y or n}?>
```

7. If you enter yes, the SMTP setup prompts appear:

```
SMTP Server ?>
SMTP User Account ?>
SMTP Password ?>
Send emails FROM user ?>
Send emails TO user(s)
  (Note: Can be a semicolon delimited list of email addresses)
?>
Send emails CC user(s)
  (Note: Can be a semicolon delimited list of email addresses)
?>
Send emails to BCC user(s)
  (Note: Can be a semicolon delimited list of email addresses)
?>
```

Make the appropriate entries, as described in this table:

For this prompt	Enter...
SMTP Server	Enter the name of the SMTP server.
SMTP User Account	Enter the user ID for the SMTP account.
SMTP Password	Enter the password for the user ID you set up as the SMTP User Account.
Send emails FROM user	Enter the email address from which the email will be sent.
Send emails TO user(s)	Enter the email addresses of the recipients you want to receive emails. Separate the email addresses with semicolons.
Send emails CC user(s)	Enter the email addresses of the recipients you want to receive courtesy copies (CC) of the emails. Separate the email addresses with semicolons.
Send emails to BCC user(s)	Enter the email addresses of the recipients you want to receive blind courtesy copies (BCC) of the emails. Separate the email addresses with semicolons.

After you answer the prompts or if you enter no to indicate you do not want to set up the error email notifications, the installation script finishes.

Installing Setup Files ... Please Wait ... New Installation Components Installed ...
--

Docupresentment installs the base system with default HTTP queues. The system should function without additional modification.

Please see *Testing the Installation* on page 33 for instructions to test a simple request using the base Docupresentment system.

SCENARIO 4: MODIFIED UPGRADE FROM VERSION 1.X

This scenario assumes the following criteria:

- You have an existing implementation of Docupresentment installed and configured on the host system.
- Docupresentment 12.6.3 will be installed into a fresh installation directory and you will manually move any existing INI files and custom code specific to your installation to the Docupresentment 12.6.3 installation directory.
- If you are using Docupresentment IDSRUNRP functionality, this scenario also assumes that Documaker Server is installed and configured on the host system.

To perform a modified upgrade from Docupresentment version 1.x, you will complete these tasks:

- *Installing Docupresentment 12.6.3 RTE* on page 24
- *Installing Documaker Bridge Shared Objects* on page 26
- *Testing Your System* on page 26
- *Customizing Your Docupresentment 12.6.3 Environment* on page 27

INSTALLING DOCUPRESENTMENT 12.6.3 RTE

Follow these steps to install Docupresentment 12.6.3 RTE:

1. Download the Docupresentment 12.6.3 RTE and the Shared Objects - Documaker Bridge 12.6.3 installation scripts from the Oracle Software Delivery Cloud site to a directory where you have execute permissions.

Note The Shared Objects - Documaker Bridge version must match the Documaker Server system installed on the host system in both version and patch level.

2. Execute the Docupresentment 12.6.3 RTE installation script.

Enter the installation path by either overriding the default installation directory location or pressing Enter to accept the default (`/home/userid/docupresentment`).

```

*** Docupresentment 12.6.3 (Type RTE) Installation/Update ***
Loading, Please Wait ...

Please select an Installation/Update Directory:
Press <Enter> to accept default:
</home/userid/docupresentment>
?>

```


3. Confirm the installation directory or correct it if a mistake was made when overriding the default.

```
Install Docupresentation 12.6(RTE) to  
</home/userid/docupresentation>?  
{y or n}?>y
```

Install/Update in progress. Please wait..

Updated Base Components ...

4. Define the path of the 32-bit JRE directory (currently Docupresentation Bridges will not run correctly with a 64-bit JRE). Accept the default detected by the installation:

```
Where is your 32-bit Java Run-time (JRE) Location?  
(Example: /usr/jdk/jdk1.6.0_24/jre)
```

JRE Version=java version "1.8.x"

Installing Setup Files ...

Please Wait ...

New Installation Components Installed ...

RTE Installation Complete

INSTALLING DOCUMAKER BRIDGE SHARED OBJECTS

Follow these steps to install the Documaker Bridge shared objects:

1. Enter the installation path. Either override the default installation directory or press Enter to accept the default (</home/userid/docupresentation/docserv>). Please note you must enter the same path (through the.../docserv level) that was supplied during the Docupresentation 12.6.3 RTE installation. For this example, use Shared Objects - Documaker Bridge 12.6.3

```

*** Documaker RP Shared Objects Bridge 12.6.3 Installation/Update ***
Loading, Please Wait ...

Please identify your Docupresentation Installation/Update
Directory: Note: Docupresentation directory must already exist.
Press <Enter> to accept default:
</home/userid/docupresentation/docserv>
?>

```

2. Confirm the installation directory path or correct, if necessary.

```

Install Documaker RP Shared Objects Bridge 12.6 to
</home/userid/docupresentation/docserv>?
{y or n}?>y

Installation/Update in progress. Please wait...
Updated Base Components ...

Installing Setup Files ...
Please Wait ...
New Documaker RP Shared Objects Bridge Installation Components Installed ...

Setting up docserv.xml to use jre located at </usr/java6/jre> ...

Installation Complete.

```

TESTING YOUR SYSTEM

Docupresentation installs the base system with default HTTP queues. The system should function without additional modification.

Please see *Testing the Installation* on page 33 for instructions to test a simple request using the base Docupresentation system.

CUSTOMIZING YOUR DOCUPRESENTMENT 12.6.3 ENVIRONMENT

Once the base system has been installed and tested, you can begin the process of moving customizations from the existing Docupresentment installation to the Docupresentment 12.6.3 directories.

Note Client customizations and configurations can vary greatly in both complexity and degree of customization. Therefore, it is highly recommended that you contact your Consulting Services representative for help in planning the transition properly. The following steps deal with the basic INI and XML configuration files that are shared among all client installations.

1. Rename or move the following INI and XML files in the new installation's docserv directory. These are the base Docupresentment files and will be replaced with the client configuration files: dap.ini, dsi.ini, docclnt.ini, docserv.ini, docclient.xml, and docserv.xml.
2. Copy the following files from the existing installation's docserv directory to the new installation's docserv directory: dap.ini, dsi.ini, docclnt.ini, docserv.ini, and any client specific INI files.
3. Modify any directory references in the copied INI files to correctly reference the new Docupresentment installation location.
4. Copy the client MRL to the new installation. Typically, the client MRL will be located in the docserv/mstres directory.
5. Create the docserv.xml and docclient.xml files using the iniconvert.sh utility. The following are the steps to perform the conversion:

- At the docserv directory of the new installation, enter:

```
./iniconvert.sh docserv.ini DocumentServerConvert.xml Docserv.xml
```

- At the docserv directory of the new installation, enter:

```
./iniconvert.sh dsi.ini DocumentClientConvert.xml Docclient.xml
```

These steps create the docserv.xml and docclient.xml files that Docupresentment 12.6.3 uses for processing. These files replace the docserv.ini and the docclient.ini files used in previous versions of Docupresentment.

Once you move all client components to the new installation directories, see *Testing the Installation* on page 33 to test the installation again.

SCENARIO 5: MODIFIED UPGRADE FROM VERSION 2.X

This scenario assumes the following criteria:

- You have an existing implementation of Docupresentment installed and configured on the host system.
- Docupresentment 12.6.3 will be installed into a fresh installation directory and you will manually move any existing INI files and custom code specific to your installation to the Docupresentment 12.6.3 installation directory.
- If you are using Docupresentment IDSRunRP functionality, this scenario also assumes that Documaker Server is installed and configured on the host system.

To perform a modified upgrade from Docupresentment version 2.x, you will complete these tasks:

- *Installing Docupresentment 12.6.3 RTE* on page 28
- *Installing Documaker Bridge Shared Objects* on page 30
- *Testing Your System* on page 30
- *Customizing Your Docupresentment 12.6.3 Environment* on page 31

INSTALLING DOCUPRESENTMENT 12.6.3 RTE

Follow these steps to install Docupresentment 12.6.3 RTE:

1. Download the Docupresentment 12.6.3 RTE and the Shared Objects - Documaker Bridge 12.6.3 installation scripts from the Oracle Software Delivery Cloud site to a directory where you have execute permissions.

Note The Shared Objects - Documaker Bridge version must match the Documaker Server system installed on the host system in both version and patch level.

2. Execute the Docupresentment 12.6.3 RTE installation script.

Enter the installation path by either overriding the default installation directory location or pressing Enter to accept the default (/home/userid/docupresentment).

```

*** Docupresentment 12.6 (Type RTE) Installation/Update ***
Loading, Please Wait ...

Please select an Installation/Update Directory:
Press <Enter> to accept default:
</home/userid/docupresentment>
?>

```

3. Confirm the installation directory or correct it if a mistake was made when overriding the default.

```
Install Docupresentment 12.6 (RTE) to  
</home/userid/docupresentment>?  
{y or n}?>y
```

Install/Update in progress. Please wait...

Updated Base Components ...

4. Define the path of the 32-bit JRE directory (currently Docupresentment Bridges will not run correctly with a 64-bit JRE). Accept the default detected by the installation:

```
Where is your 32-bit Java Run-time (JRE) Location?  
(Example: /usr/jdk/jdk1.6.0_24/jre)
```

```
JRE Version=java version "1.8.x"
```

```
Installing Setup Files ...
```

```
Please Wait ...
```

```
New Installation Components Installed ...
```

```
RTE Installation Complete
```

INSTALLING DOCUMAKER BRIDGE SHARED OBJECTS

Follow these steps to install the Documaker Bridge shared objects:

1. Enter the installation path. Either override the default installation directory or press Enter to accept the default (</home/userid/docupresentation/docserv>). Please note you must enter the same path (through the.../docserv level) that was supplied during the Docupresentation 12.6.3 Docupresentation 12.6.3 RTE installation. For this example, use Shared Objects - Documaker Bridge 12.6.3.

```
*** Documaker RP Shared Objects Bridge 12.6 Installation/Update ***
Loading, Please Wait ...
```

```
Please identify your Docupresentation Installation/Update
Directory: Note: Docupresentation directory must already exist.
Press <Enter> to accept default:
</home/userid/docupresentation >
?>
```

2. Confirm the installation directory path or correct, if necessary.

```
Install Documaker RP Shared Objects Bridge 12.6 to
</home/userid/docupresentation >?
{y or n}?>y
```

```
Installation/Update in progress. Please wait...
Updated Base Components ...
```

```
Installing Setup Files ...
Please Wait ...
New Documaker RP Shared Objects Bridge Installation Components Installed ...
```

```
Setting up docserv.xml to use jre located at </usr/java6/jre> ...
```

```
Installation Complete.
```

TESTING YOUR SYSTEM

Docupresentation installs the base system with default HTTP queues. The system should function without additional modification.

Please see *Testing the Installation* on page 33 for instructions to test a simple request using the base Docupresentation system.

CUSTOMIZING YOUR DOCUPRESENTMENT 12.6.3 ENVIRONMENT

Once the base system has been installed and tested, you can begin the process of moving customizations from the existing Docupresentment installation to the Docupresentment 12.6.3 directories.

Note Client customizations and configurations can vary greatly in both complexity and degree of customization. Therefore, it is highly recommended that you contact your Consulting Services representative for help in planning the transition and executing the migration.

These steps deal with the basic XML configuration files that are shared by all client installations:

1. Create a backup copy of the following INI and XML files in the new installation's docserv directory (these are the base Docupresentment files and will be modified): dap.ini, dsi.ini, docclient.xml, and docserv.xml.
2. Modify any directory references in these INI and XML files to correctly reference the new Docupresentment installation location.
3. Copy the client MRL to the new installation. Typically, the client MRL will be located in the docserv/mstres directory.
4. Modify the base Docupresentment 12.6.3 docserv.xml and docclient.xml files to include these changes:
 - Queuing systems. Modify the existing queuing settings to use the queuing methodology your environment uses. Also modify the dsi.ini file to include the queuing changes.
 - Customized client request types. The base Docupresentment system includes only base client request types. Client specific customized request types should be copied and pasted to the new docserv.xml file. If any of the request types include a path that includes the new Docupresentment installation path, be sure to modify those paths in the request types.
 - Configurations. You can copy the dap.ini file from your existing Docupresentment 2.x environment to the newly-created Docupresentment 12.6.3 environment (be sure to create a backup copy first in the docserv directory). This makes sure the configuration information is available to the Docupresentment 12.6.3 installation.

Once you move all client components to the new installation directories, see *Testing the Installation* on page 33 to test the installation again.

SCENARIO 6: PATCH UPGRADE OF A VERSION 12.6.3 ENVIRONMENT

Follow these steps to apply a patch to an Docupresentment 12.6.3 installation:

1. Download the Docupresentment 12.6.3 RTE script to a directory where you have execute permissions.
2. Execute the Docupresentment 12.6.3 RTE installation script.

Enter the installation path: You must point the installation to the existing directory or the user-specified directory name.

```

*** Docupresentment 12.6.3 (Type RTE) Installation/Update ***
Loading, Please Wait ...

Please select an Installation/Update Directory:
Press <Enter> to accept default:
</home/userid/docupresentment>
?>

```

3. The system detects that a previous version of Docupresentment is resident. You must choose to back up and update, or quit. Oracle highly recommends that you choose option 1 for back up and update. When doing so, the installation script will create a back up directory under the docserv directory.

```

Docupresentment installation </home/userid/docupresentment>
for version <12.6> already exist.

Please select a upgrade type
1 = Backup and Upgrade Installation
2 = Upgrade Installation
3 = Quit
?>1

```

4. Confirm the chosen path or edit if necessary. Once correct, enter **Y** to complete the installation:

```

Update Docupresentment 12.6.3 (RTE) to
</home/userid/docupresentment>?
{y or n}?>y

Install/Update in progress. Please wait...
Updated Base Components ...

RTE Installation Complete

```

Docupresentment installs the base system with default HTTP queues. The system should function without additional modification.

Please see *Testing the Installation* on page 33 for instructions to test a simple request using the base Docupresentment system.

TESTING THE INSTALLATION

Follow these steps to test your installation:

1. Start the Docupresentment 12.6.3 sever by navigating to the `../docserv` directory for the installation and enter:

```
./docserver.sh start
```

Note Note that the shell script to start Docupresentment changed from `docserv.sh` to `docserver.sh`. There are also additional use suffixes of: `start`, `stop`, and `status` that must be appended to the end of the `docserver.sh` script commands.

Previously, to stop the Docupresentment server, you would issue the `Ctrl+C` command. Beginning with version 12.6.3, you must issue the command `docserver.sh stop` to end the session.

2. Enter this command:

```
./threads.sh display=yes reqtype=SSS
```

3. The following output should be directed to the Docupresentment console screen. The error count should be zero (0) and the results variable should be SUCCESS:

```
./threads.sh display=yes reqtype=sss
<?xml version="1.0" encoding="UTF-8"?>
<SOAP-ENV:Envelope xmlns:SOAP-ENV="http://schemas.xmlsoap.org/soap/
envelope/">
  <SOAP-ENV:Body>
    <DSIMSG VERSION="100.025.0-2.5.0.1268">
      <CTLBLOCK>
        <UNIQUE_ID>0EE5C3F8-108A-18CF-8347-720ACB23</UNIQUE_ID>
        <REQTYPE>sss</REQTYPE>
      </CTLBLOCK>
      <MSGVARS>
        <VAR NAME="ERRORCOUNT">0</VAR>
        <VAR NAME="IDSGUID">9F7A5823-727C-F6A6-BD66-
8F12D8482F1E</VAR>
        <VAR NAME="IDSHOSTNAME">slc03dtm.us.oracle.com</VAR>
        <VAR NAME="LASTRESTART">Nov 30, 2014 8:39:39 PM UTC</VAR>
        <VAR NAME="RESTARTCOUNT">0</VAR>
        <VAR NAME="RESULTS">SUCCESS</VAR>
        <VAR NAME="SERVERTIMESPENT">0.011</VAR>
        <VAR NAME="SUCCESSCOUNT">8</VAR>
        <VAR NAME="UPTIME">Nov 30, 2014 8:39:39 PM UTC</VAR>
        <VAR NAME="WARNINGCOUNT">0</VAR>
        <ROWSET NAME="LIBRARIES">
          <ROW NUM="1">
            <VAR NAME="DATE">Nov 30 2014</VAR>
            <VAR NAME="NAME">dsicrule</VAR>
            <VAR NAME="TIME">02:46:57</VAR>
            <VAR NAME="VERSION">200.025.001</VAR>
          </ROW>
          <ROW NUM="2">
            <VAR NAME="DATE">Nov 30 2014</VAR>
            <VAR NAME="NAME">DSIOS2</VAR>
            <VAR NAME="TIME">02:47:00</VAR>
            <VAR NAME="VERSION">200.025.002</VAR>
          </ROW>
          <ROW NUM="3">
            <VAR NAME="DATE">Nov 30 20142014</VAR>
            <VAR NAME="NAME">dsijava</VAR>
            <VAR NAME="TIME">02:47:05</VAR>
```

```
<VAR NAME="VERSION">200.025.001</VAR>
</ROW>
<ROW NUM="4">
  <VAR NAME="DATE">Nov 30 2014</VAR>
  <VAR NAME="NAME">jexec</VAR>
  <VAR NAME="TIME">02:47:06</VAR>
  <VAR NAME="VERSION">200.025.001</VAR>
</ROW>
<ROW NUM="5">
  <VAR NAME="DATE">Nov 30 2014</VAR>
  <VAR NAME="NAME">ARC</VAR>
  <VAR NAME="TIME">12:20:09</VAR>
  <VAR NAME="VERSION">12,2,0,19054</VAR>
</ROW>
<ROW NUM="6">
  <VAR NAME="DATE">Nov 30 2014</VAR>
  <VAR NAME="NAME">CAR</VAR>
  <VAR NAME="TIME">12:13:22</VAR>
  <VAR NAME="VERSION">12,2,0,19054</VAR>
</ROW>
<ROW NUM="7">
  <VAR NAME="DATE">Nov 30 2014</VAR>
  <VAR NAME="NAME">DAL</VAR>
  <VAR NAME="TIME">12:20:45</VAR>
  <VAR NAME="VERSION">12,2,0,19054</VAR>
</ROW>
<ROW NUM="8">
  <VAR NAME="DATE">Nov 30 2014</VAR>
  <VAR NAME="NAME">DB5</VAR>
  <VAR NAME="TIME">12:13:36</VAR>
  <VAR NAME="VERSION">12,2,0,19054</VAR>
</ROW>
<ROW NUM="9">
  <VAR NAME="DATE">Nov 30 2014</VAR>
  <VAR NAME="NAME">DB</VAR>
  <VAR NAME="TIME">12:12:14</VAR>
  <VAR NAME="VERSION">12,2,0,19054</VAR>
</ROW>
<ROW NUM="10">
  <VAR NAME="DATE">Nov 30 2014</VAR>
  <VAR NAME="NAME">DPR</VAR>
  <VAR NAME="TIME">12:25:45</VAR>
  <VAR NAME="VERSION">12,2,0,19054</VAR>
</ROW>
<ROW NUM="11">
  <VAR NAME="DATE">Nov 30 2014</VAR>
  <VAR NAME="NAME">DS</VAR>
  <VAR NAME="TIME">12:12:36</VAR>
  <VAR NAME="VERSION">12,2,0,19054</VAR>
</ROW>
<ROW NUM="12">
  <VAR NAME="DATE">Nov 30 2014</VAR>
  <VAR NAME="NAME">DXM</VAR>
  <VAR NAME="TIME">12:10:35</VAR>
  <VAR NAME="VERSION">12,2,0,19054</VAR>
</ROW>
<ROW NUM="13">
  <VAR NAME="DATE">Nov 30 2014</VAR>
  <VAR NAME="NAME">FAP</VAR>
  <VAR NAME="TIME">12:11:01</VAR>
  <VAR NAME="VERSION">12,2,0,19054</VAR>
</ROW>
<ROW NUM="14">
  <VAR NAME="DATE">Nov 30 2014</VAR>
```

```
<VAR NAME="NAME">FNT</VAR>
<VAR NAME="TIME">12:16:33</VAR>
<VAR NAME="VERSION">12,2,0,19054</VAR>
</ROW>
<ROW NUM="15">
  <VAR NAME="DATE">Nov 30 2014</VAR>
  <VAR NAME="NAME">GRF</VAR>
  <VAR NAME="TIME">12:13:27</VAR>
  <VAR NAME="VERSION">12,2,0,19054</VAR>
</ROW>
<ROW NUM="16">
  <VAR NAME="DATE">Nov 30 2014</VAR>
  <VAR NAME="NAME">INI</VAR>
  <VAR NAME="TIME">12:10:08</VAR>
  <VAR NAME="VERSION">12,2,0,19054</VAR>
</ROW>
<ROW NUM="17">
  <VAR NAME="DATE">Nov 30 2014</VAR>
  <VAR NAME="NAME">LBY</VAR>
  <VAR NAME="TIME">12:20:59</VAR>
  <VAR NAME="VERSION">12,2,0,19054</VAR>
</ROW>
<ROW NUM="18">
  <VAR NAME="DATE">Nov 30 2014</VAR>
  <VAR NAME="NAME">LOG</VAR>
  <VAR NAME="TIME">12:14:57</VAR>
  <VAR NAME="VERSION">12,2,0,19054</VAR>
</ROW>
<ROW NUM="19">
  <VAR NAME="DATE">Nov 30 2014</VAR>
  <VAR NAME="NAME">MTC</VAR>
  <VAR NAME="TIME">12:26:41</VAR>
  <VAR NAME="VERSION">12,2,0,19054</VAR>
</ROW>
<ROW NUM="20">
  <VAR NAME="DATE">Nov 30 2014</VAR>
  <VAR NAME="NAME">PDF</VAR>
  <VAR NAME="TIME">12:18:04</VAR>
  <VAR NAME="VERSION">12,2,0,19054</VAR>
</ROW>
<ROW NUM="21">
  <VAR NAME="DATE">Nov 30 2014</VAR>
  <VAR NAME="NAME">PRT</VAR>
  <VAR NAME="TIME">12:13:06</VAR>
  <VAR NAME="VERSION">12,2,0,19054</VAR>
</ROW>
<ROW NUM="22">
  <VAR NAME="DATE">Nov 30 2014</VAR>
  <VAR NAME="NAME">TIF</VAR>
  <VAR NAME="TIME">12:13:51</VAR>
  <VAR NAME="VERSION">12,2,0,19054</VAR>
</ROW>
<ROW NUM="23">
  <VAR NAME="DATE">Nov 30 2014</VAR>
  <VAR NAME="NAME">USR</VAR>
  <VAR NAME="TIME">12:20:14</VAR>
  <VAR NAME="VERSION">12,2,0,19054</VAR>
</ROW>
<ROW NUM="24">
  <VAR NAME="DATE">Nov 30 2014</VAR>
  <VAR NAME="NAME">UTL</VAR>
  <VAR NAME="TIME">12:10:31</VAR>
  <VAR NAME="VERSION">12,2,0,19054</VAR>
</ROW>
```

```
<ROW NUM="25">
  <VAR NAME="DATE">Nov 30 2014</VAR>
  <VAR NAME="NAME">VMM</VAR>
  <VAR NAME="TIME">12:09:55</VAR>
  <VAR NAME="VERSION">12,2,0,19054</VAR>
</ROW>
<ROW NUM="26">
  <VAR NAME="DATE">Nov 30 2014</VAR>
  <VAR NAME="NAME">XER</VAR>
  <VAR NAME="TIME">12:17:42</VAR>
  <VAR NAME="VERSION">12,2,0,19054</VAR>
</ROW>
<ROW NUM="27">
  <VAR NAME="DATE">Nov 30 2014</VAR>
  <VAR NAME="NAME">XMC</VAR>
  <VAR NAME="TIME">12:16:06</VAR>
  <VAR NAME="VERSION">12,2,0,19054</VAR>
</ROW>
</ROWSET>
</MSGVARS>
</DSIMSG>
</SOAP-ENV:Body>
</SOAP-ENV:Envelope>
```

```
Total test time=522 ms.
Transactions run <1>
Success count <1>
Error count <0>
```

UNINSTALLING THE SYSTEM

To uninstall Docupresentation on UNIX/Linux, just remove the base installation directory and all its sub-directories. It may also be necessary to remove any HTML and CGI-BIN directories if they are external to the base installation directory.

Chapter 2

Installing Docupresentment on Windows

This chapter provides information on installing Docupresentment on Windows-based machines.

You will find this information:

- *Overview* on page 39
- *Downloading the Software* on page 40
- *Installing Shared Objects* on page 46
- *Installing the Docupresentment Client* on page 48
- *Testing Your Installation* on page 56
- *Setting Up the System as a Service* on page 59
- *Uninstalling the System* on page 63
- *Troubleshooting the Client* on page 64
- *Installing the Docupresentment with a Response File* on page 67

Note For information on system requirements, see [System Requirements Guide](#)

OVERVIEW

The files that make up Docupresentation and its bridges include:

- Java programs executed by a Java Runtime for your operating system
- Dynamically Shared Objects (DSOs)

In Windows environments, DSOs are typically named **.dll*. In UNIX environments, DSOs are often named *lib*.so* or *lib*.sl*.

- HTML content pages
- HTML templates

There are several Java components that run on a server machine, including a server that handles back-end processing and communicates with installed bridge products from Documaker. Java client components that can be run from a J2EE application server, and a CGI client for older clients. The bridge products let you...

- Read Documaker archives
- Search and retrieve documents from Documanager via the Internet
- Convert Metacode and AFP print streams created by the Documerge and Documaker systems and stored in a Documanager database into PDF files
- Use Docuflex as a composition engine for Docupresentation on Windows

Enterprise Web Processing Services

Docupresentation version 12.6.3 for Windows includes Enterprise Web Processing Services (EWPS). EWPS makes it easier to integrate applications, providing a set of web services for accessing the Documaker forms library and initiating real-time publishing operations. This helps you deliver the information requested by your clients, prospects, employees, and business partners.

When you install Docupresentation on Windows, the installation routine creates the following directory and copies into it the `ewps-axis2.war` file:

```
..\docserv\webservices  
ewps-axis2.war
```

See [EWPS Guide](#) for more information.

DOWNLOADING THE SOFTWARE

Docupresentment is available for download via the Oracle Software Delivery Cloud website. The installation contains the server (including the SDK), bridges, and client. Having separate installations for the required components lets you pick the version of Documaker components separately from Docupresentment. The latest version of Documaker is version 12.6.3. Generally, you would want the latest version and patch level of the software. You will find links to the latest patch levels of previous versions of Documaker at the My Oracle Support website:

<https://support.oracle.com>

Installing the correct version of Shared Objects - Documaker Bridge is especially important if you plan to use Docupresentment to run Documaker. The installation of other bridges, such as the Documanager Bridge, is optional.

Note If you do not already have a JRE (JRE 1.8.172 for Linux) already installed, JRE 1.8 is installed with Docupresentment Server 12.6.3. After installing the J2SE Java Runtime Environment (JRE) version 1.8 and Docupresentment, you will need to install a version of Shared Objects - Documaker Bridge.

USING THE ORACLE SOFTWARE DELIVERY CLOUD

Oracle applications are available for download from the [Oracle Software Delivery Cloud](#) website. The process includes:

- Logging in and agreeing to the terms and restrictions
- Searching for the applications you want to download
- Downloading those applications

Note To download the latest patches for the Oracle software you have already installed, visit the My Oracle Support site at this web address:

<https://support.oracle.com>

To download the latest documentation, visit the Oracle Technology Network (OTN) website at this web address:

<http://www.oracle.com/technetwork/>

Before you begin

The Oracle Software Delivery Cloud site lets you download versions of Oracle applications. Files on the Oracle Software Delivery Cloud are available in ZIP format. Once you download the files you need, extract the files in the ZIP file to proceed with the software installation.

Note You can download the corresponding product documentation from the Oracle Technology Network (OTN) site:

<http://www.oracle.com/technetwork/documentation/insurance-097481.html>

You will need Acrobat Reader or a similar program to view the PDF documentation. You can download Acrobat Reader at Adobe's site (www.adobe.com).

Follow these instructions to download Oracle applications:

1. First, go to the Oracle Software Delivery Cloud website:
<https://edelivery.oracle.com>
2. Sign in with your Oracle account. If you do not have an Oracle account, you can register for an account [here](#).
3. Review and accept the Terms and Restrictions.
4. Select Oracle Applications from the Product Pack list or you can search the Product.
5. Once you have selected the desired program, select the desired platform.
6. The selected products are then listed. To remove them, click the X (cross) which is adjacent to the product.
7. Once you have selected the desired product and platform, click Continue to proceed.
8. License agreement is displayed. Once you are ready to proceed, check the checkbox, then click Continue.
9. Installations are displayed. To individually download files click on the filename, to download all files click on the Download All button.
10. The Oracle Software Delivery Cloud prompts you to open or save the zipped file and then starts the download.

While you can save the file on any machine you choose, we recommend you save the file onto the machine where you plan to run it. You must unzip the file on the platform for which it was intended. The length of time it takes to download an application depends on the size of the download, your connection speed, and the amount of traffic on the site.

11. Click Sign Out when you finish downloading the files you need.

INSTALLING THE DOCUPRESENTMENT SERVER


Before you start the installation...

- Be familiar with how your web server is set up. You will need to know if the Docupresentation site uses Secured Socket Layer (SSL) and the IP address of the client PC
- Exit all programs currently running. The setup routine also lets you install various other components required to run the Docupresentation. If these files are already installed *and in use* when the setup routine runs, conflicts will arise.

Note Be aware that when you update an existing installation, your existing configuration files *are not* changed. This lets you preserve any customizations you have made in those files. Furthermore, keep in mind that if you uninstall the system, *all* configuration files are removed.


After you download and save the Docupresentation installation to the proper location, start the Docupresentation Server setup wizard ODDS12.6.3.b#####W32.exe (where b##### represents the build number) as that is the name of the installer.).

Once the setup routine starts, follow the instructions which appear on your screen.




1. Close all open applications then click Next to continue. The Select Destination Directory window appears.

2. Click Browse to select the directory into which you want to install DocuPresentment. Click Next to continue.



3. The Select Components window appears.



4. Choose the components you want to install. Click Next to continue. The Select Start Menu Folder window appears. The Select Additional Tasks window appears.

Select Additional Tasks
Which additional tasks should be performed?

Select the additional tasks you would like Setup to perform while installing Oracle Docupresentation Server, then click Next.

Configure Watchdog SMTP Email Settings

Server Address *

From *

User Name

Password

Email Recipients *

Example: user1@company.com;user2@company.com

Email CC Recipients

Email BCC Recipients

install-4j

< Back Next > Cancel

5. Use the Select Additional Tasks window to optionally configure your Watchdog SMTP email settings. Click Next to continue when you are finished. The Installing window appears. This window tracks the setup wizard's progress as it installs Docupresentation on your computer.
6. Once the basic installation finishes, the Docupresentation Server setup wizard asks if you want to configure Docupresentation Server as a service.

Configure Oracle Docupresentation Server as Service
Would you like to configure Oracle Docupresentation Server as a service?

Start Oracle Docupresentation Server as a Service

Service Name: Oracle Docupresentation Watchdog Server


install-4j

Next > Cancel

Click the Start Docupresentation Server as a Service option and enter a name for the service or accept the default name.

Click Next. The Complete Installation window appears.

7. Click Finish to complete the installation process.



Congratulations, you have installed Docupresentation Server. Now proceed to the next topic, *Installing Shared Objects* on page 46.

INSTALLING SHARED OBJECTS

As mentioned above, installation of the Shared Objects - Documaker Bridge component is required to install Documaker Server components, even if your installation does not use Documaker Bridge.

To download shared objects from the Internet, go to the Oracle Software Delivery Cloud site at:

<http://edelivery.oracle.com/>

After you download and save the shared objects installation to the proper location, start the shared objects installation routine by clicking Start, Run and entering this command:


```
(drive letter): ODSOvvv.00.xxxxxW32.exe
```

where *vvv* is the version number, such as 12.6.3 and *xxxxx* is the build number.

The Setup wizard starts.

Using the Setup wizard

Follow these steps to install shared objects using the Setup wizard




1. Once the Setup wizard starts, click Next to continue.

The Choose Docupresentation Installation Path window appears.

2. Click Browse to specify the directory path of the Docupresentation installation to which you want to add Shared Objects and click Next to continue.


The Select Components window appears.

3. Choose the components you want to install.



Click Next to continue. The Installing window appears. This window tracks the setup wizard's progress as it installs the Shared Objects you selected on your computer.

4. Click Finish to exit the setup wizard once the installation finishes.



Congratulations, you have installed the Docupresentation and the Shared Objects. Now proceed to the next topic, *Installing the Docupresentation Client*.


INSTALLING THE DOCUPRESENTMENT CLIENT

You can install the Docupresentation Client on Windows by downloading it from the Internet. To download shared objects from the Internet, go to the Oracle Software Delivery Cloud site at:

<http://edelivery.oracle.com/>


After you download and save the Docupresentation Client installation to the proper location, start the Docupresentation Client setup wizard ODDC12.6.3.####W32.exe (where #### represents the build number) as that is the name of the installer.

1. Once the setup routine starts, follow the instructions which appear on your screen.




2. Close all open applications then click Next to continue. The Select Destination Directory window appears.
3. Click Browse to select the directory into which you want to install the Docupresentation Client and click Next to continue.

The Select Components window appears.



4. Choose the components you want to install and click Next to continue.



The installation routine installs the Docupresentation Client, then shows the Select queuing System window. See *Selecting a queuing Method* on page 50 for more information.


SELECTING A QUEUING METHOD

Use the Select a queuing System window to optionally configure your Docupresentation Client queuing method. The wizard modifies the Docupresentation Client to communicate with one of these queuing systems:

- HTTP
- ActiveMQ
- IBM MQ or WebSphere MQ or
- MSMQ

Note You can also choose to set up a queuing system other than the ones pre-defined in the installer. Be aware that if you choose this option, you must make sure the queuing system is accessible by the Docupresentation Client.

Choose the queuing method you want to use on the Select a queuing System window:



Click Next.

A configuration wizard lets you enter queue-specific information for each queuing method. The default queue is HTTP.

Using HTTP

If chose HTTP queues, the Configure the HTTP queuing System window appears:

Configure the HTTP Queueing System
Please configure the HTTP Queueing System

ORACLE

Please enter the following information to configure Oracle Docupresentation Client for your chosen Queuing Manager:

Server Address: localhost

Port: 39152 Default

install-fj

< Back Next > Cancel

For HTTP queues, enter the Server Address and Port Number of the Docupresentation Server and click Next.

Using ActiveMQ

If you chose ActiveMQ, the Configure the ActiveMQ queuing System window appears:

Configure the ActiveMQ Queueing System
Please configure the ActiveMQ Queueing System

ORACLE

Please enter the following information to configure Oracle Docupresentation Client for your chosen Queuing Manager:

Server Address: localhost

Port: 39152 Default

Input Queue:

Output Queue:

install-fj

< Back Next > Cancel

For ActiveMQ queues, enter the Input Queue and Output Queue for the ActiveMQ Server and click Next.

Using WebSphere MQ

If you chose WebSphere MQ, the Configure the WebSphere MQ queuing System window appears:

Configure the WebSphere MQ Queueing System **ORACLE**
Please configure the WebSphere MQ Queueing System

Please enter the following information to configure Oracle Docupresentation Client for your chosen Queuing Manager:

Bindings Mode

Server Address: localhost

Port: 39152

Queue Channel:

Input Queue:

Output Queue:

Queue Manager:

install-4j

< Back Next > Cancel


For WebSphere MQ queues, you can choose to use Bindings Mode.

To	Then
Use Bindings Mode	Make sure the Bindings Mode field is checked, then specify the Input Queue, Output Queue, and the Queue Manager for the WebSphere MQ Server.
Not use Bindings Mode	Uncheck the Bindings Mode field and specify the Server Address, Port, Queue Channel, Input Queue, Output Queue, and the Queue Manager for the WebSphere MQ Server.

When finished entering the necessary fields, click Next.

Using MSMQ


If you chose MSMQ, the Configure the MSMQ queuing System window appears:



For MSMQ queues, enter the Input Queue and Output Queue for the MSMQ Server and click Next.


Setting up another queue

If you choose to set up another queuing system, the following message appears to remind you to take the steps necessary to make your queuing system accessible by the Docupresentation Client.



Testing Your Connection

To make sure the Docupresentation Client can connect to the Docupresentation Server, click the Test Connection button.



Note Docupresentation Server and the queuing system you chose have to be running to test the Docupresentation Client.


If the test is successful, the below message appears “connection to Docupresentation Server Successful”.



This window indicates that the Docupresentation Client is configured correctly and is successfully communicating with the Docupresentation Server. Click Ok, then click Next.

The Complete Installation window appears. Click Finish to complete the installation.

Congratulations, you have installed the Docupresentation Server, Shared Objects, and Docupresentation Client Now proceed to the next topic, *Testing Your Installation*.



TESTING YOUR INSTALLATION

To test your Docupresentation installation, open a command window and follow these steps.

1. Start Docupresentation Server by entering this command in the c:\docserv directory:

```
docserver.bat
```

You should now see a window similar to the following window:

```
2018-04-27 13:37:57,316 INFO [WD-Watchdog-main]-[?:?]com.docucorp.watchdog.Wat
chdog.watch: Oracle Docupresentation Watchdog Server
2018-04-27 13:37:57,331 INFO [WD-Watchdog-main]-[?:?]com.docucorp.watchdog.Wat
chdog.watch: Version 12.6.2
2018-04-27 13:37:57,335 INFO [WD-Watchdog-main]-[?:?]com.docucorp.watchdog.Wat
chdog.watch: Running Java version 1.8.0_111-b14 from Oracle Corporation on Windo
ws 8.1 6.3 with 2 processors.
2018-04-27 13:37:57,934 INFO [WD-Watchdog-main]-[?:?]com.docucorp.watchdog.Wat
chdog.watch: Watchdog Server Ready
2018-04-27 13:38:00,282 INFO [Router] - Set up logging using logconf.xml
2018-04-27 13:38:00,293 INFO [Router] - Oracle Docupresentation Router.
2018-04-27 13:38:00,295 INFO [Router] - Running Java version 1.8.0_111-b14 from
Oracle Corporation
2018-04-27 13:38:00,475 INFO [IDS-1-DocumentServer-main] - Set up logging using
logconf.xml
2018-04-27 13:38:00,672 INFO [IDS-2-DocumentServer-main] - Set up logging using
logconf.xml
2018-04-27 13:38:00,723 INFO [IDS-1-BLP] - Oracle Docupresentation.
2018-04-27 13:38:00,726 INFO [IDS-1-BLP] - Version 12.6.2-12.6.2.33515
2018-04-27 13:38:00,727 INFO [IDS-1-BLP] - Running Java version 1.8.0_111-b14 f
rom Oracle Corporation on Windows 8.1 6.3 with 2 processors.
2018-04-27 13:38:00,917 INFO [IDS-2-BLP] - Oracle Docupresentation.
2018-04-27 13:38:00,919 INFO [IDS-2-BLP] - Version 12.6.2-12.6.2.33515
2018-04-27 13:38:00,921 INFO [IDS-2-BLP] - Running Java version 1.8.0_111-b14 f
rom Oracle Corporation on Windows 8.1 6.3 with 2 processors.
2018-04-27 13:38:01,268 INFO [IDS-1-BLP] - Business Logic Processor started
2018-04-27 13:38:01,390 INFO [IDS-2-BLP] - Business Logic Processor started
DocuMaker shared objects version 12.6,2,33515
DocuMaker shared objects version 12.6,2,33515
```

Docupresentation Server has started when you see the following:

```
Business Logic Processor started
```

```
Documaker shared objects version 12.6.xxxxx
```

Note xxxxx refers to the build number.

2. By default, two instances of Docupresentation Server 12.6.3 will start. Go to the Docupresentation Client Box open a command prompt. Then go to the Docupresentation Client directory, such as c:\docclnt, and enter this command:

```
dsiexw32.exe
```



```
Microsoft Windows [Version 5.2.3790]
(C) Copyright 1985-2003 Microsoft Corp.

C:\docclnt>dsiexw32_
```


3. You should now see a window similar to the following window:

```

Name = LIBRARIES17.VERSION Value = 12,6,2,33515
Name = LIBRARIES18.DATE Value = Apr 26 2018
Name = LIBRARIES18.NAME Value = LBV
Name = LIBRARIES18.TIME Value = 21:42:50
Name = LIBRARIES18.VERSION Value = 12,6,2,33515
Name = LIBRARIES19.DATE Value = Apr 26 2018
Name = LIBRARIES19.NAME Value = LGN
Name = LIBRARIES19.TIME Value = 21:43:04
Name = LIBRARIES19.VERSION Value = 12,6,2,33515
Name = LIBRARIES20.DATE Value = Apr 26 2018
Name = LIBRARIES20.NAME Value = LOG
Name = LIBRARIES20.TIME Value = 21:34:51
Name = LIBRARIES20.VERSION Value = 12,6,2,33515
Name = LIBRARIES21.DATE Value = Apr 26 2018
Name = LIBRARIES21.NAME Value = PRT
Name = LIBRARIES21.TIME Value = 21:32:15
Name = LIBRARIES21.VERSION Value = 12,6,2,33515
Name = LIBRARIES22.DATE Value = Apr 26 2018
Name = LIBRARIES22.NAME Value = USR
Name = LIBRARIES22.TIME Value = 21:42:05
Name = LIBRARIES22.VERSION Value = 12,6,2,33515
Name = LIBRARIES23.DATE Value = Apr 26 2018
Name = LIBRARIES23.NAME Value = UTL
Name = LIBRARIES23.TIME Value = 21:30:02
Name = LIBRARIES23.VERSION Value = 12,6,2,33515
Name = LIBRARIES24.DATE Value = Apr 26 2018
Name = LIBRARIES24.NAME Value = UMM
Name = LIBRARIES24.TIME Value = 21:28:31
Name = LIBRARIES24.VERSION Value = 12,6,2,33515
C:\docclnt>

```

If you receive these results, Docupresentation is installed and running properly.

4. You can run another verification test using threads.bat by typing the following command at the command prompt:

```
threads.bat reqtype=sss display=yes
```

```

Microsoft Windows [Version 5.2.3790]
(C) Copyright 1985-2003 Microsoft Corp.
C:\docclnt>Dsitestw reqtype=sss display=yes

```

You should now see a window similar to the following window:

```
</ROW>
<ROW NUM="23">
  <VAR NAME="DATE">Apr 26 2018</VAR>
  <VAR NAME="NAME">UTL</VAR>
  <VAR NAME="TIME">21:30:02</VAR>
  <VAR NAME="VERSION">12.6.2.33515</VAR>
</ROW>
<ROW NUM="24">
  <VAR NAME="DATE">Apr 26 2018</VAR>
  <VAR NAME="NAME">UMM</VAR>
  <VAR NAME="TIME">21:28:31</VAR>
  <VAR NAME="VERSION">12.6.2.33515</VAR>
</ROW>
</ROWSET>
</MSGUARS>
</DSIMSG>
</SOAP-ENV:Body>
</SOAP-ENV:Envelope>

Total test time=533 ms.

Transactions run <1>
Success count <1>
Error count <0>
C:\docclnt>
```

If you receive these results, Docupresentment is communicating via HTTP queues and the system is able to process request types successfully.


SETTING UP THE SYSTEM AS A SERVICE

Note You cannot run Docupresentment version 12.6.3 as a service using HTTP queues. To run Docupresentment as a service, you must use WebSphere MQ, ActiveMQ, or MSMQ.

To install Docupresentment as a service, open a command shell window and go to the directory into which you installed Docupresentment, such as `c:\docserv`


Next, enter this command in the `c:\docserv` directory:

```
Ds-service.bat
```



```
Command Shell
Microsoft Windows XP [Version 5.1.2600]
(C) Copyright 1985-2001 Microsoft Corp.
C:\docserv>ds-service.bat
```

You should now see a window similar to the following window:



```
Command Shell
Microsoft Windows XP [Version 5.1.2600]
(C) Copyright 1985-2001 Microsoft Corp.
C:\docserv>ds-service.bat
C:\docserv>idswdservice.exe -install "Docucorp Watchdog Server" "c:\docserv\jre\bin\client\jvm.dll" -Xmx256m -Djava.endorsed.dirs="c:\docserv\lib\endorsed" -Djava.class.path="c:\docserv\lib\DocucorpStartup.jar" -start com.docucorp.startup.Startup -params com.docucorp.watchdog.Watchdog -stop com.docucorp.startup.Startup -method stop -out "c:\docserv\watchdog-stdout.txt" -err "c:\docserv\watchdog-stderr.txt" -current "c:\docserv" -path "c:\docserv"
The Docucorp Watchdog Server automatic service was successfully installed.
C:\docserv>
```


Docupresentment has been installed as a service on Windows when you see this message:

```
The Docucorp Watchdog Server automatic service was successfully installed
```

VERIFYING DOCUPRESENTMENT WAS INSTALLED AS A SERVICE

1. Open Control Panel and choose Administrative Tools. Then choose Services to open the Services Console.


The Docupresentation watchdog service is listed as Docucorp Watchdog Server.



The Services Console lets you start and stop Docupresentation as a service.


2. When you start Docupresentation via the Services Console, you can make sure the service is running by going to Task Manager.

Here is the Docupresentation watchdog service in the Processes list.



3. Open another command prompt and go to the installation directory, such as c:\docserv, and enter this command:


```
dsiexw32.exe
```



```
Command Prompt
Microsoft Windows XP [Version 5.1.2600]
(C) Copyright 1985-2001 Microsoft Corp.

C:\Documents and Settings\ern>cd\
C:\>cd docserv
C:\docserv>dsiserv32.exe_
```

You should now see a window similar to the following window:



```
Command Prompt
Name = LIBRARIES19.NAME Value = LCN
Name = LIBRARIES19.TIME Value = 00:58:14
Name = LIBRARIES19.VERS ION Value = 400.113.010
Name = LIBRARIES20.DATE Value = Dec 12 2007
Name = LIBRARIES20.NAME Value = LOG
Name = LIBRARIES20.TIME Value = 00:51:48
Name = LIBRARIES20.VERS ION Value = 400.113.010
Name = LIBRARIES21.DATE Value = Dec 12 2007
Name = LIBRARIES21.NAME Value = PRI
Name = LIBRARIES21.TIME Value = 00:47:23
Name = LIBRARIES21.VERS ION Value = 400.113.011
Name = LIBRARIES22.DATE Value = Dec 12 2007
Name = LIBRARIES22.NAME Value = USB
Name = LIBRARIES22.TIME Value = 00:57:13
Name = LIBRARIES22.VERS ION Value = 400.113.010
Name = LIBRARIES23.DATE Value = Dec 12 2007
Name = LIBRARIES23.NAME Value = UTL
Name = LIBRARIES23.TIME Value = 00:45:20
Name = LIBRARIES23.VERS ION Value = 400.113.010
Name = LIBRARIES24.DATE Value = Dec 12 2007
Name = LIBRARIES24.NAME Value = UMM
Name = LIBRARIES24.TIME Value = 00:44:09
Name = LIBRARIES24.VERS ION Value = 400.113.003

C:\docserv>
```


If you receive these results, Docupresentment is installed and running properly as a service.

UNINSTALLING DOCUPRESENTMENT AS A SERVICE

To uninstall Docupresentment as a service, open a command window and go to the directory into which you installed Docupresentment, such as `c:\docserv`.


Next, enter this command in the `c:\docserv` directory:

```
Ds-service-uninstall.bat
```



```
Command Shell
Microsoft Windows XP [Version 5.1.2600]
(C) Copyright 1985-2001 Microsoft Corp.
C:\docserv>Ds-service-uninstall.bat_
```

You should see a window similar to this one:



```
Command Shell
Microsoft Windows XP [Version 5.1.2600]
(C) Copyright 1985-2001 Microsoft Corp.
C:\docserv>Ds-service-uninstall.bat
C:\docserv>JavaService -uninstall "Docucorp Watchdog Server"
The Docucorp Watchdog Server service was successfully uninstalled.
C:\docserv>_
```

Docupresentment has been uninstalled as a service on Windows when you see this message:

```
The Docucorp Watchdog Server automatic service was successfully
uninstalled
```

The *Docucorp Watchdog Server* entry will no longer appear in the Services Console. The Docupresentment watchdog service has been uninstalled.

UNINSTALLING THE SYSTEM

Before uninstalling Docupresentment Server, you will need to stop Oracle Docupresentment Watchdog service (idswdservice.exe). Go to the Control Panel- Services or Windows Task Manager, Processes and this option removes Docupresentment, the various bridges, and sample files.

Data files saved after you installed Docupresentment are preserved.

If necessary, you must remove the required Microsoft components separately.

Chapter 3

Troubleshooting the Client

Here are some things to check if the Docupresentment Client is not communicating with Docupresentment Server.

Note: The test connection from client to server will fail if the port numbers are not valid. Use unused port numbers to avoid this issue.

Checking the DOCCLIENT.XML File

First, make sure the docclient.xml file is set up correctly. Here is an example docclient.xml file, including all of the queue sections with ActiveMQ active:

```
<?xml version="1.0" encoding="UTF-8"?>
<configuration>
  <section name="DocumentClient" version="12.6.3">
    <section name="messaging">
      <!--JMS / ActiveMQ Section-->
      <!--Remove 'DISABLE-' to enable this section. Only one
queue section can exist at a time.-->
      <section name="queue">
        <entry
name="marshaller.class">com.docucorp.messaging.data.marshaller.SOAPM
IMEDSIMessageMarshaller</entry>
        <entry
name="queuefactory.class">com.docucorp.messaging.jms.DSIJMSJNDIMessa
geQueueFactory</entry>
        <entry name="jms.inputqueue.connectstring">resultq</
entry>
        <entry name="jms.outputqueue.connectstring">requestq</
entry>
        <entry name="jms.qcf.name">queueConnectionFactory</
entry>
        <entry
name="jms.initial.context.factory">org.apache.activemq.jndi.ActiveMQ
InitialContextFactory</entry>
      </section>
      <!--HTTP Section-->
      <!--Remove 'DISABLE-' to enable this section. Only one
queue section can exist at a time.-->
      <section name="DISABLE-queue">
        <entry
name="marshaller.class">com.docucorp.messaging.data.marshaller.SOAPM
IMEDSIMessageMarshaller</entry>
        <entry
name="queuefactory.class">com.docucorp.messaging.http.DSIHTTPMessage
QueueFactory</entry>
        <entry name="http.url">http://localhost:49352</entry>
        <entry name="http.reuse.ports">15</entry>
        <entry name="inputqueue.maxwaitseconds">30</entry>
      </section>
      <!--MQSeries Section-->
      <!--Remove 'DISABLE-' to enable this section. Only one
queue section can exist at a time.-->
      <section name="DISABLE-queue">
        <entry
name="marshaller.class">com.docucorp.messaging.data.marshaller.SOAPM
IMEDSIMessageMarshaller</entry>
```



```

        <entry
name="queuefactory.class">com.docucorp.messaging.mqseries.DSIMQMessageQueueFactory</entry>
        <entry name="mq.queue.manager"></entry>
        <entry name="mq.inputqueue.name">RESULTQ</entry>
        <entry name="mq.inputqueue.maxwaitseconds">5</entry>
        <entry name="mq.outputqueue.name">REQUESTQ</entry>
        <!-- Remove 'DISABLE-' from the following line to use
in TCP/IP 'client' mode. -->
        <!-- Leave disabled to use in 'bindings' mode. -->
        <entry name="DISABLE-mq.tcpip.host">127.0.0.1</entry>
        <entry name="mq.queue.channel">SYSTEM.DEF.SVRCONN</
entry>
        <entry name="mq.tcpip.port">1414</entry>
        <entry name="mq.conn.userid">appUserid</entry>
        <entry name="mq.conn.password">appPassword</entry>
    </section>
    <!--MSMQ Section-->
    <!--Remove 'DISABLE-' to enable this section. Only one
queue section can exist at a time.-->
    <section name="DISABLE-queue">
        <entry
name="marshaller.class">com.docucorp.messaging.data.marshaller.SOAPM
IMEDSIMessageMarshaller</entry>
        <entry
name="queuefactory.class">com.docucorp.messaging.msmq.DSIMSMQMessage
QueueFactory</entry>
        <entry name="msmq.server.name">localhost</entry>
        <entry name="msmq.inputqueue.name">private$\RESULTQ</
entry>
        <entry name="msmq.outputqueue.name">private$\REQUESTQ</
entry>
        <entry name="msmq.timeout">30000</entry>
        <entry name="msmq.expiry">1800000</entry>
    </section>
    </section>
    <!-- messaging section -->
</section>
<!-- DocumentClient -->
</configuration>

```

Checking the CLASSPATH and other Environment Variables

The following values are added to the CLASSPATH variable when you install the Docupresentation Client:

```

CLASSPATH=C:\docclnt\clientlib\DocucorpMsg.jar;C:\docclnt\clientlib\
DocumentServer.jar;C:\docclnt\clientlib\commons-
collections.jar;C:\docclnt\clientlib\commons-
fileupload.jar;C:\docclnt\clientlib\commons-
pool.jar;C:\docclnt\clientlib\DocuCorpUtil.jar;C:\docclnt\clientlib\
DSIJavaMsg.jar;C:\docclnt\clientlib\IDSJSP.jar;C:\docclnt\clientlib\
jdom.jar;C:\docclnt\clientlib\xerces.jar;C:\docclnt\clientlib\log4j.
jar;

```

The following values are added to the PATH variable when you install the Docupresentation Client:

```

PATH=C:\docclnt;C:\docclnt\jre\bin\client;C:\docclnt\jre\bin;e:\docc
lnt\.\.install4j

```

These values are added to the following variables when you install the Docupresentation Client:

```

ids_client_configuration=C:\docclnt\docclient.xml

```

```
java_endorsed_dirs=C:\docclnt\clientlib\endorsed
logging_client_configuration=C:\docclnt\logclientconf.xml
```

Installing Third-Party JAR Files

Note If you are using IBM MQ (WebSphere MQ or MQ Series) or ActiveMQ for the queuing method, you must make the IBM MQ or ActiveMQ jar files available to Docupresentment. See the “Installing Third-Party Jar Files” section of the [Docupresentment Guide](#) for more information.

INSTALLING THE DOCUPRESENTMENT WITH A RESPONSE FILE

You can run the Docupresentment in unattended mode from the command line. To do this you must create a response file to provide the information the installer needs. A response file is a text file which contains the information a user would typically provide while running the Setup wizard or responding to command-line prompts. This information is in name=value format.

To create a response file that contains the necessary data, first run the command-line installer in one of these ways:

- Using default mode, with no arguments. After the installation finishes, the installer creates a response file named *response.varfile*.
- Using the command-line installation with the *-console* parameter. This lets you specify the name you want to assign to the response file.

After the installation finishes, the installer creates the response file and stores it in the *.install4j* directory. This file contains name=value data captured during the installation process. You can edit this file if necessary to modify the values. Here is an example:

```
#install4j response file for (application/version)
#Wed Mar 16 16:53:12 EDT 2011
sys.languageId=en
sys.installationDir=d:\ (application/version)
```

You can then pass this response file to the installer using the *-varfile* parameter. For example, to run the installer in unattended mode using a response file, include these parameters:

```
-q -console -c -varfile varfilename
```

Parameter	Description
-----------	-------------

-q	Runs the installer in unattended mode.
-console	If the installer is executed in unattended installation mode (-q) and you include -console as the second parameter, a console is allocated on Windows that displays the output of the installer.
-c	Runs the installer in the console mode.
-varfile	<i>Varfilename</i> specifies the name of the response.varfile to use. You can include a full path.

Note For more information about response files and install4j installations, go to this website:
<http://resources.ej-technologies.com/install4j/help/doc/>

Here is an example:

```
(application/version).exe -q -console -c -varfile  
response.varfile
```

Here is an example of the output you will see:

```
Extracting files...  
Downloading ...  
Extracting files...  
Finishing installation..
```