Oracle® Database Gateway for APPC Installation and Configuration Guide





Oracle Database Gateway for APPC Installation and Configuration Guide, 23c for Microsoft Windows

F47552-02

Copyright © 2006, 2023, Oracle and/or its affiliates.

Primary Author: Rhonda Day

Contributing Authors: Vira Goorah, Govind Lakkoju, Peter Wong, Juan Pablo Ahues-Vasquez, Peter Castro, Charles Benet

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software, software documentation, data (as defined in the Federal Acquisition Regulation), or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs) and Oracle computer documentation or other Oracle data delivered to or accessed by U.S. Government end users are "commercial computer software," "commercial computer software documentation," or "limited rights data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, reproduction, duplication, release, display, disclosure, modification, preparation of derivative works, and/or adaptation of i) Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs), ii) Oracle computer documentation and/or iii) other Oracle data, is subject to the rights and limitations specified in the license contained in the applicable contract. The terms governing the U.S. Government's use of Oracle cloud services are defined by the applicable contract for such services. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle®, Java, and MySQL are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Inside are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Epyc, and the AMD logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

Contents

Preface

Audience	Xi
Documentation Accessibility	X
Related Documents	Xi
Conventions	xi
Introduction to Oracle Database Gateway for APPC	
1.1 Overview of the Gateway	1-1
1.2 Features of the Gateway	1-2
1.3 Terms	1-3
1.4 Architecture of the Gateway	1-5
1.5 Implementation of the Gateway	1-6
1.6 Communication with the Gateway	1-6
1.7 Remote Procedural Call Functions	1-6
1.7.1 Description of RPC Functions	1-7
1.7.1.1 Remote Transaction Initiation	1-7
1.7.1.2 Data Exchange	1-7
1.7.1.3 Remote Transaction Termination	1-8
1.8 Transaction Types for Gateway Using SNA	1-8
1.9 Transaction Types for Gateway Using TCP/IP	1-8
Release Information	
2.1 Product Set	2-1
2.2 Changes and Enhancements	2-1
2.2.1 Gateway Password Encryption Tool	2-1
2.2.2 Partial IPv6 Support	2-1
2.3 Known Restrictions	2-1
2.3.1 Known Restrictions for the Gateway	2-1
2.3.2 Known Restrictions for PGAU	2-2



3 System Requirements

3.1 Har	dware Requirements	3-1
3.1.1	Processor Requirements	3-1
3.1.2	Memory Requirements	3-1
3.1.3	Network Attachment Requirements	3-1
3.1.4	·	3-2
	tware Requirements	3-2
3.2.1	Operating System Requirements	3-2
3.2.2		3-2
3.2.3	Oracle Database Requirements	3-2
3.2.4	Oracle Networking Product Requirements	3-2
3.2.5	IBM Mainframe Requirements	3-3
Installir	ng the Gateway	
4.1 Befo	ore You Begin	4-1
4.2 Plar	nning to Upgrade or Migrate the Gateway	4-2
4.2.1	Performing Pre-Upgrade Procedures	4-2
4.2.2	Upgrade and Migration Considerations	4-2
4.2.3	Restoration	4-3
4.3 Perf	forming Preinstallation Procedures	4-3
4.3.1	Gateway Installation Methods	4-4
4.4 Inst	alling the Gateway Software	4-4
4.5 Usir	ng Windows User Account as Oracle Home User	4-4
4.6 Inst	allation Steps	4-4
4.0 11150		4 5
4.6.1	Step 1: Log On to Windows System	4-5
	Step 1: Log On to Windows System Step 2: Ensure Minimum Amount of Disk Space	
4.6.1		4-5
4.6.1 4.6.2	Step 2: Ensure Minimum Amount of Disk Space	4-5 4-5 4-5 4-5
4.6.1 4.6.2 4.6.3	Step 2: Ensure Minimum Amount of Disk Space Step 3: Stop All Oracle Services	4-5 4-5
4.6.1 4.6.2 4.6.3 4.6.4	Step 2: Ensure Minimum Amount of Disk Space Step 3: Stop All Oracle Services Step 4: Insert the Gateway Product Installation Media	4-5 4-5 4-5
4.6.1 4.6.2 4.6.3 4.6.4 4.6.5 4.6.6	Step 2: Ensure Minimum Amount of Disk Space Step 3: Stop All Oracle Services Step 4: Insert the Gateway Product Installation Media Step 5: Start the Oracle Universal Installer	4-5 4-5 4-5 4-5 4-6
4.6.1 4.6.2 4.6.3 4.6.4 4.6.5 4.6.6	Step 2: Ensure Minimum Amount of Disk Space Step 3: Stop All Oracle Services Step 4: Insert the Gateway Product Installation Media Step 5: Start the Oracle Universal Installer Step 6: Step Through the Oracle Universal Installer	4-5 4-5 4-5 4-5
4.6.1 4.6.2 4.6.3 4.6.4 4.6.5 4.6.6	Step 2: Ensure Minimum Amount of Disk Space Step 3: Stop All Oracle Services Step 4: Insert the Gateway Product Installation Media Step 5: Start the Oracle Universal Installer Step 6: Step Through the Oracle Universal Installer 6.6.1 Oracle Universal Installer on Windows Platforms	4-5 4-5 4-5 4-6 4-6



6 Configuring the SNA Communication Package on Windows

6.1	Usir	ng SNA Security Validation	6-1
6.2	Prod	cessing Inbound Connections	6-1
6.3	Con	figuring Your Microsoft Host Integration Server	6-2
(6.3.1	Independent Versus Dependent LUs	6-2
	6.3.2	Location of Sample SNA Server Definitions	6-3
(6.3.3	HIS Definition Types	6-3
	6.3.4	Methods of Creating SNA Server Definitions for the Gateway	6-3
6.4	Crea	ating SNA Server Definitions on Microsoft Host Integration Server	6-4
(6.4.1	Server Selection	6-4
	6.4.2	Link Service Definition	6-4
	6.4.3	Connection Definition	6-4
	6.4.4	Local LU Definition	6-5
	6.4.5	Mode Definition	6-5
	6.4.6	Remote LU Definition	6-6
	6.4.7	CPI-C Symbolic Destination Name	6-6
6.5	Con	figuring an IBM Communications Server	6-7
	6.5.1	Independent And Dependent LUs	6-7
(6.5.2	Definition Types	6-8
6.6	Crea	ating IBM Communications Server Definitions for the Gateway	6-8
(6.6.1	Creating the Configuration	6-8
(6.6.2	Creating the Node	6-8
	6.6.3	Creating Devices	6-9
(6.6.4	Choosing the Device Type	6-9
	6.6.5	Configuring a LAN Device	6-9
	6.6.6	Creating Peer Connections	6-9
	6.6.7	Defining the Link Station	6-9
	6.6.8	Defining the Adjacent Node	6-9
	6.6.9	Creating Local LUs	6-10
	6.6.10	Defining Local LUs	6-10
	6.6.11	Creating Partner LUs	6-10
	6.6.12	Defining Partner LUs	6-10
	6.6.13	Creating the CPI-C Side Information Profile	6-10
6.7	Test	ing the Connection	6-10
6.8	Res	ume Configuration of the Gateway	6-11
Со	nfigu	uring the OLTP	
7.1	Con	figuring the OLTP for Your SNA Environment	7-1



7

8	Configuring the	e Gatewa	v Using SNA	Communication	Protoco
\cup			,		

8.1 Before You Begin	8-1
8.2 Preparing to Configure a Gateway Installation/Upgrade	8-1
8.3 Integrating Server Configuration: First-Time Gateway Installations	8-3
8.4 Upgrading or Migrating the Oracle Database from Previous Gateways	8-6
8.4.1 If You Must Reinstall Package Specifications	8-7
8.4.2 Upgrading PGAU from Previous Gateway Releases	8-7
8.5 Configuring the Oracle Database for Gateways to Coexist	8-8
8.6 Optional Configuration Steps to Permit Multiple Users	8-8
8.7 Configuring the Gateway	8-10
8.8 Configuring Commit-Confirm	8-12
8.8.1 Configuring the Oracle Database for Commit-Confirm	8-12
8.8.2 Configuring Gateway Initialization Parameters for Commit-Confirm	8-13
8.8.3 Configuring the OLTP for Commit-Confirm	8-13
8.9 Verifying the Gateway Installation and OLTP Configuration	8-14
8.9.1 Verifying the Gateway Installation	8-14
8.9.2 Verifying the OLTP Configuration	8-15
8.9.2.1 CICS Verification	8-15
8.9.2.2 IMS/TM Verification	8-16
8.9.2.3 APPC/MVS Verification	8-16
8.9.3 Verifying OLTP Configuration for Commit-Confirm	8-17
8.10 Performing Postinstallation Procedures	8-18
8.10.1 Installing Sample Applications	8-18
Configuring the Gateway Using TCP/IP Communication Protocol	
9.1 Before You Begin	9-1
9.2 Preparing to Configure a Gateway Installation/Upgrade	9-1
9.3 Configuring the Oracle Database : First Time Installation	9-3
9.4 Upgrading or Migrating the Oracle Database from Previous Gateways	9-7
9.4.1 If You Must Reinstall Package Specifications	9-7
9.4.2 Upgrading PGAU from Previous Gateway Releases	9-8
9.5 Optional Configuration Steps to Permit Multiple Users	9-8
9.6 Configuring TCP/IP for the Gateway	9-11
9.7 Configuring the Gateway	9-11
9.8 Loading the PGA_TCP_IMSC Table	9-12
9.9 Verifying the Gateway Installation and OLTP Configuration	9-13
9.9.1 Verifying the Gateway Installation	9-13



9

	Verifying the OLTP Configuration	
S	.9.2.1 IMS/TM Verification	9-1
	erforming Postinstallation Procedures	9-1
9.10.	1 Installing Sample Applications	9-1
Securi	ty Requirements	
10.1 O	verview of Security Requirements	10-
10.2 A	uthenticating Application Logons	10-
10.3 D	efining and Controlling Database Links	10
10.3.	1 Link Accessibility	10-
10.3.	2 Links and CONNECT Clauses	10
10.4 U	sing SNA Security Validation	10-
10.4.	1 Specifying SNA Conversation Security	10-
1	0.4.1.1 SNA Security Option SECURITY=NONE	10-
1	0.4.1.2 SNA Security Option SECURITY=PROGRAM	10
10.5 T	CP/IP Security	10
10.5.	1 Specifying TCP/IP Conversation Security	10
1	0.5.1.1 TCP/IP Security Option SECURITY=NONE	10
	0.5.1.2 TCP/IP Security Option SECURITY=PROGRAM	10-
1	· ·	
1 10.6 P	0.5.1.2 TCP/IP Security Option SECURITY=PROGRAM asswords in the Gateway Initialization File	
1 10.6 P Migrat	0.5.1.2 TCP/IP Security Option SECURITY=PROGRAM asswords in the Gateway Initialization File ng from Existing Gateways	10-
10.6 P Migrat 11.1 M	0.5.1.2 TCP/IP Security Option SECURITY=PROGRAM asswords in the Gateway Initialization File ng from Existing Gateways igrating an Existing Gateway Instance to New Release Using SNA Protocol	10-
10.6 P Migrat 11.1 M 11.1.	0.5.1.2 TCP/IP Security Option SECURITY=PROGRAM asswords in the Gateway Initialization File ng from Existing Gateways igrating an Existing Gateway Instance to New Release Using SNA Protocol Step 1: Install the New Release	10- 11- 11-
10.6 P Migrat 11.1 M 11.1. 11.1.	0.5.1.2 TCP/IP Security Option SECURITY=PROGRAM asswords in the Gateway Initialization File ng from Existing Gateways igrating an Existing Gateway Instance to New Release Using SNA Protocol Step 1: Install the New Release Step 2: Transfer initsid.ora Gateway Initialization File Parameters	11- 11- 11-
10.6 P Migrat 11.1 M 11.1. 11.1. 11.1.	o.5.1.2 TCP/IP Security Option SECURITY=PROGRAM asswords in the Gateway Initialization File ng from Existing Gateways igrating an Existing Gateway Instance to New Release Using SNA Protocol Step 1: Install the New Release Step 2: Transfer initsid.ora Gateway Initialization File Parameters Backout Considerations When Migrating to New Releases	11- 11- 11- 11-
10.6 P Migrat 11.1 M 11.1. 11.1. 11.1.	o.5.1.2 TCP/IP Security Option SECURITY=PROGRAM asswords in the Gateway Initialization File Ing from Existing Gateways igrating an Existing Gateway Instance to New Release Using SNA Protocol Step 1: Install the New Release Step 2: Transfer initsid.ora Gateway Initialization File Parameters Backout Considerations When Migrating to New Releases Oracle Net Considerations	11- 11- 11- 11- 11-
10.6 P Migrat 11.1 M 11.1. 11.1. 11.1. 11.1.	o.5.1.2 TCP/IP Security Option SECURITY=PROGRAM asswords in the Gateway Initialization File Ing from Existing Gateways Igrating an Existing Gateway Instance to New Release Using SNA Protocol Step 1: Install the New Release Step 2: Transfer initsid.ora Gateway Initialization File Parameters Backout Considerations When Migrating to New Releases Oracle Net Considerations Parameter Changes: Version 4 to 12c Release 2 (12.2) of the Gateway	11- 11- 11- 11- 11- 11-
10.6 P Migrat 11.1 M 11.1. 11.1. 11.1. 11.1. 11.1.	o.5.1.2 TCP/IP Security Option SECURITY=PROGRAM asswords in the Gateway Initialization File Ing from Existing Gateways Igrating an Existing Gateway Instance to New Release Using SNA Protocol Step 1: Install the New Release Step 2: Transfer initsid.ora Gateway Initialization File Parameters Backout Considerations When Migrating to New Releases Oracle Net Considerations Parameter Changes: Version 4 to 12c Release 2 (12.2) of the Gateway Parameter Changes: Version 8 or Earlier to Gateway 12c Release 2 (12.2)	11- 11- 11- 11- 11- 11-
10.6 P Migrat 11.1 M 11.1. 11.1. 11.1. 11.1.	o.5.1.2 TCP/IP Security Option SECURITY=PROGRAM asswords in the Gateway Initialization File Ing from Existing Gateways Igrating an Existing Gateway Instance to New Release Using SNA Protocol Step 1: Install the New Release Step 2: Transfer initsid.ora Gateway Initialization File Parameters Backout Considerations When Migrating to New Releases Oracle Net Considerations Parameter Changes: Version 4 to 12c Release 2 (12.2) of the Gateway Parameter Changes: Version 8 or Earlier to Gateway 12c Release 2 (12.2)	11 11 11 11 11 11
10.6 P Migrat 11.1 M 11.1. 11.1. 11.1. 11.1. 11.1. 11.1. 11.1.	o.5.1.2 TCP/IP Security Option SECURITY=PROGRAM asswords in the Gateway Initialization File Ing from Existing Gateways Igrating an Existing Gateway Instance to New Release Using SNA Protocol Step 1: Install the New Release Step 2: Transfer initsid.ora Gateway Initialization File Parameters Backout Considerations When Migrating to New Releases Oracle Net Considerations Parameter Changes: Version 4 to 12c Release 2 (12.2) of the Gateway Parameter Changes: Version 8 or Earlier to Gateway 12c Release 2 Migrating from Gateway Release 9.0.1 or 9.2.0 to Gateway 12c Release 2	11. 11. 11. 11. 11. 11.
10.6 P Migrat 11.1 M 11.1. 11.1. 11.1. 11.1. 11.1. 11.1. 11.1.	o.5.1.2 TCP/IP Security Option SECURITY=PROGRAM asswords in the Gateway Initialization File Ing from Existing Gateways Igrating an Existing Gateway Instance to New Release Using SNA Protocol Step 1: Install the New Release Step 2: Transfer initsid.ora Gateway Initialization File Parameters Backout Considerations When Migrating to New Releases Oracle Net Considerations Parameter Changes: Version 4 to 12c Release 2 (12.2) of the Gateway Parameter Changes: Version 8 or Earlier to Gateway 12c Release 2 (12.2) Migrating from Gateway Release 9.0.1 or 9.2.0 to Gateway 12c Release 2 (12.2) Igrating from an Existing Gateway Using SNA to TCP/IP	11. 11. 11. 11. 11. 11. 11.
10.6 P Migrat 11.1 M 11.1. 11.1. 11.1. 11.1. 11.1. 11.1. 11.1. 11.1.	o.5.1.2 TCP/IP Security Option SECURITY=PROGRAM asswords in the Gateway Initialization File Ing from Existing Gateways Igrating an Existing Gateway Instance to New Release Using SNA Protocol Step 1: Install the New Release Step 2: Transfer initsid.ora Gateway Initialization File Parameters Backout Considerations When Migrating to New Releases Oracle Net Considerations Parameter Changes: Version 4 to 12c Release 2 (12.2) of the Gateway Parameter Changes: Version 8 or Earlier to Gateway 12c Release 2 (12.2) Migrating from Gateway Release 9.0.1 or 9.2.0 to Gateway 12c Release 2 (12.2) Igrating from an Existing Gateway Using SNA to TCP/IP To Use Existing TIPs with Existing Side Profile Definitions	11 11 11 11 11 11 11
Migrat 11.1 M 11.1. 11.1. 11.1. 11.1. 11.1. 11.2 M 11.2. Gatew	o.5.1.2 TCP/IP Security Option SECURITY=PROGRAM asswords in the Gateway Initialization File Ing from Existing Gateways Igrating an Existing Gateway Instance to New Release Using SNA Protocol I Step 1: Install the New Release Step 2: Transfer initsid.ora Gateway Initialization File Parameters Backout Considerations When Migrating to New Releases Oracle Net Considerations Parameter Changes: Version 4 to 12c Release 2 (12.2) of the Gateway Parameter Changes: Version 8 or Earlier to Gateway 12c Release 2 (12.2) Migrating from Gateway Release 9.0.1 or 9.2.0 to Gateway 12c Release 2 (12.2) Igrating from an Existing Gateway Using SNA to TCP/IP To Use Existing TIPs with Existing Side Profile Definitions ay Initialization Parameters for SNA Protocol	11. 11. 11. 11. 11. 11. 11.
Migrat 11.1 M 11.1. 11.1. 11.1. 11.1. 11.1. 11.2 M 11.2. Gatew A.1 PG	o.5.1.2 TCP/IP Security Option SECURITY=PROGRAM asswords in the Gateway Initialization File Ing from Existing Gateways Igrating an Existing Gateway Instance to New Release Using SNA Protocol I Step 1: Install the New Release 2 Step 2: Transfer initsid.ora Gateway Initialization File Parameters 3 Backout Considerations When Migrating to New Releases 4 Oracle Net Considerations 5 Parameter Changes: Version 4 to 12c Release 2 (12.2) of the Gateway 6 Parameter Changes: Version 8 or Earlier to Gateway 12c Release 2 (12.2) 7 Migrating from Gateway Release 9.0.1 or 9.2.0 to Gateway 12c Release 2 (12.2) Igrating from an Existing Gateway Using SNA to TCP/IP 1 To Use Existing TIPs with Existing Side Profile Definitions A Parameters	11- 11- 11- 11- 11- 11- 11-
Migrat 11.1 M 11.1. 11.1. 11.1. 11.1. 11.1. 11.2 M 11.2. Gatew A.1 PG A.2 PG	o.5.1.2 TCP/IP Security Option SECURITY=PROGRAM asswords in the Gateway Initialization File Ing from Existing Gateways Igrating an Existing Gateway Instance to New Release Using SNA Protocol I Step 1: Install the New Release Step 2: Transfer initsid.ora Gateway Initialization File Parameters Backout Considerations When Migrating to New Releases Oracle Net Considerations Parameter Changes: Version 4 to 12c Release 2 (12.2) of the Gateway Parameter Changes: Version 8 or Earlier to Gateway 12c Release 2 (12.2) Migrating from Gateway Release 9.0.1 or 9.2.0 to Gateway 12c Release 2 (12.2) Igrating from an Existing Gateway Using SNA to TCP/IP To Use Existing TIPs with Existing Side Profile Definitions ay Initialization Parameters for SNA Protocol	10- 10- 11- 11- 11- 11- 11- 11- 11- 11-



B.1 Ga	eway Initialization Parameter File Using TCP/IP	B-2
B.2 Out	put for the pg4tcpmap Tool	B-3
B.2.1	Sample listener.ora File for a Gateway Using TCP/IP	B-4
B.2.2	Sample tnsnames.ora File for a Gateway Using TCP/IP	B-5
COntidi	uration Worksheet	



List of Figures

1-1	Relationship of Gateway and Oracle Database on Windows	1-4
1-2	Gateway Architecture	1-5
6-1	Relationship Between SNA Server Definitions and Host VTAM	6-11



List of Tables

1-1	RPC Functions and Commands in Oracle Database Gateway for APPC and Remote Host	1-7
4-1	The Oracle Universal Installer: Steps for Installing Oracle Database Gateway for APPC	4-6
A-1	PGA Parameters for Oracle Database Gateway for APPC Using SNA	A-1
B-1	PGA Parameters for Oracle Database Gateway for APPC Using TCP/IP for IMS Connect	B-2
D-1	Parameters for Configuring Gateway and Communication Protocols	D-1



Preface

The Oracle Database Gateway for APPC provides Oracle applications with seamless access to IBM mainframe data and services through Remote Procedure Call (RPC) processing.

Refer to the *Oracle Database Installation Guide* for Microsoft Windows and to the certification matrix on My Oracle Support for the most up-to-date list of certified hardware platforms and operating system versions. The My Oracle Support Web site can be found at:

https://support.oracle.com

Audience

Read this guide if you are responsible for tasks such as:

- determining hardware and software requirements
- installing, configuring, or administering an Oracle Database Gateway for APPC
- developing applications that access remote host databases through the gateway using either the SNA communication protocol or the TCP/IP for IMS Connect communication protocol.
- · determining security requirements
- determining and resolving problems

Before using this guide to administer the gateway, you should understand the fundamentals of the Windows operating system, SNA Server, the Database Gateways, PL/SQL and the Oracle database.

Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc.

Access to Oracle Support

Oracle customers that have purchased support have access to electronic support through My Oracle Support. For information, visit http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info or visit http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs if you are hearing impaired.

Related Documents

The Oracle Database Gateway for APPC Installation and Configuration Guide for Microsoft Windows is included as a part of your product shipment. Also included is:

Oracle Database Gateway for APPC User's Guide



You might also need Oracle database and Oracle Net documentation. The following is a useful list of the Oracle publications that may be referenced in this book:

- Oracle Database Installation Guide for Microsoft Windows
- Oracle Database Administrator's Guide
- Oracle Database Development Guide
- Oracle Database Concepts
- Oracle Database Error Messages
- Oracle Database Net Services Administrator's Guide
- Oracle Database PL/SQL Language Reference
- Oracle Call Interface Programmer's Guide

In addition to the Oracle documentation, ensure that you have required documentation for your platform, for your operating system, and for your communications packages.

The following IBM documentation may be useful:

IMS Connect Guide and Reference

The title of the IBM publication was accurate at the time of the publication of this guide. Titles and structure of these documents are subject to change. For other operating system, SNA communication package, and TCP/IP package references, refer to the appropriate vendor documentation for your system.

Conventions

Examples of input and output for the gateway and Oracle environment are shown in a special font:

```
C:\> mkdir \ORACLE\your_name
```

All output is shown as it appears. For input, the list of conventions and their meanings are as follows:

- example text: Words or phrases, such as mkdir and ORACLE, must be entered exactly as spelled and in the letter case shown. In this example, mkdir must be entered in lowercase letters and ORACLE in uppercase letters.
- *italic text*: Italicized uppercase or lowercase, such as *your_name*, indicates that you must substitute a word or phrase, such as the actual directory name.
- **BOLD text** Or **bold italic TEXT**: Bold words or phrases refer to a file or directory structure, such as a directory, path, or file ID.
- ...: Ellipses indicate that the preceding item can be repeated. You can enter an arbitrary number of similar items.
- { }: Curly braces indicate that one of the enclosed arguments is required. Do not enter the braces themselves.
- |: Vertical lines separate choices.
- []: Square brackets enclose optional clauses from which you can choose one or none. Do not enter the brackets themselves.

Other punctuation, such as commas, quotation marks or the pipe symbol (|) must be entered as shown unless otherwise specified. Directory names, file IDs and so on



appear in the required letter case in examples. The same convention is used when these names appear in text, and the names are highlighted in **bold**. The use of *italics* indicates that those portions of a file ID that appear in *italics* can vary.

Gateway commands, file IDs reserved words, MS-DOS commands, keywords and environment variables appear in uppercase in examples and text. Reserved words must always be entered as shown; they have reserved meanings within the Oracle system.

SQL*Plus Prompts

The SQL*Plus prompt, SQL>, appears in SQL statement and SQL*Plus command examples. Enter your response at the prompt. Do not enter the text of the prompt, SQL>, in your response.

MS-DOS Prompts

The MS-DOS prompt, $C:\$, appears in MS-DOS command examples. Enter your response at the prompt. Do not enter the text of the prompt, $C:\$, in your response.

PGAU Prompts

The PGAU prompt, PGAU>, appears in PGAU command examples. Enter your response at the prompt. Do not enter the text of the prompt, PGAU>, in your response.

Directory Names

Throughout this document, there are references to the directories in which product-related files reside. <code>%ORACLE_HOME%</code> is used to represent the Oracle home directory. This is the default location for Oracle products. If you have installed into a location other than <code>%ORACLE_HOME%</code>, replace all references to <code>%ORACLE_HOME%</code> with the drive and path specification you have used.



1

Introduction to Oracle Database Gateway for APPC

The Oracle Database Gateway for APPC (the "gateway") enables users to initiate transaction program execution on remote online transaction processors (OLTPs.) The Oracle Database Gateway for APPC can establish connection with OLTP using the SNA communication protocol. The gateway can also use TCP/IP for IMS Connect to establish communication with the OLTP through TCP/IP. The gateway provides Oracle applications with seamless access to IBM mainframe data and services through Remote Procedural Call (RPC) processing. The gateway can access any application capable of using the CPI-C API either directly or through a TP monitor such as CICS.

The following topics discuss the architecture, uses, and features of the gateway.

- Overview of the Gateway
- Features of the Gateway
- Terms
- Architecture of the Gateway
- Implementation of the Gateway
- Communication with the Gateway
- Remote Procedural Call Functions
- Transaction Types for Gateway Using SNA
- Transaction Types for Gateway Using TCP/IP

1.1 Overview of the Gateway

The Oracle Database Gateway for APPC extends the Remote Procedural Call (RPC) facilities available with the Oracle database. The gateway enables any client application to use PL/SQL to request execution of a remote transaction program (RTP) residing on a host. The gateway provides RPC processing to systems using the SNA APPC (Advanced Program-to-Program Communication) protocol and to systems using TCP/IP for IMS Connect protocol. This architecture allows efficient access to data and transactions available on the IBM mainframe and IMS, respectively.

The gateway requires no Oracle software on the remote host system. Thus, the gateway uses existing transactions with little or no programming effort on the remote host.

For gateways using SNA:

The use of a generic and standard protocol, APPC, allows the gateway to access a multitude of systems. The gateway can communicate with virtually any APPC-enabled system, including IBM Corporation's CICS on any platform and IBM Corporation's IMS and APPC/MVS. These transaction monitors provide access to a broad range of systems, allowing the gateway to access many datastores, including VSAM, DB2 (static SQL), IMS, and others.



The gateway can access any application capable of using the CPI-C API either directly or through a TP monitor such as CICS.

1.2 Features of the Gateway

The Oracle Database Gateway for APPC provides the following benefits:

TCP/IP support for IMS Connect

This release of the gateway includes TCP/IP support for IMS Connect, giving users a choice of whether to use the SNA or TCP/IP communication protocol. IMS Connect is an IBM product which allows TCP/IP clients to trigger execution of IMS transactions. The gateway can use a TCP/IP communication protocol to access IMS Connect, which triggers execution of IMS transactions. If you choose to use TCP/IP, then there is no SNA involvement with this configuration. Related to this new feature of the gateway is:

The pg4tcpmap tool. This release of the gateway includes a new tool whose purpose is to map the information from your side profile name to TCP/IP and IMS Connect. For more information about the gateway mapping tool, refer to Chapter 6, of the *Oracle Database Gateway for APPC User's Guide*, and to Gateway Configuration Using TCP/IP Communication Protocol in this guide.

Fast interface

The gateway is optimized so that remote execution of a program is achieved with minimum network traffic. The interface to the gateway is an optimized PL/SQL stored procedure specification (called the TIP or transaction interface package) precompiled in the Oracle database . Because there are no additional software layers on the remote host system, overhead occurs only when the program processes.

Location transparency

Client applications need not be operating system-specific. For example, your application can call a program on a CICS Transaction Server for z/OS. If you move the program to a CICS region on pSeries, then you need not change the application.

Application transparency

Users calling applications that execute a remote transaction program are unaware that a request is sent to a host.

Flexible interface

You can use the gateway to interface with existing procedural logic or to integrate new procedural logic into an Oracle database environment.

Oracle database integration

The integration of the Oracle database with the gateway enables the gateway to benefit from existing and future Oracle features. For example, the gateway can be called from an Oracle stored procedure or database trigger.

Transactional support

The gateway and the Oracle database allow remote transfer updates and Oracle database updates to be performed in a coordinated fashion.

· Wide selection of tools

The gateway supports any tool or application that supports PL/SQL.



PL/SQL code generator

The Oracle Database Gateway for APPC provides a powerful development environment, including:

- a data dictionary to store information relevant to the remote transaction
- a tool to generate the PL/SQL Transaction Interface Package, or TIP
- a report utility to view the information stored in the gateway dictionary
- a complete set of tracing and debugging facilities
- a wide set of samples to demonstrate the use of the product against datastores such as DB2, IMS, and CICS.
- Site autonomy and security

The gateway provides site autonomy, allowing you to do such things as authenticate users. It also provides role-based security compatible with any security package running on the mainframe computer.

Automatic conversion

Through the TIP, the following conversions are performed:

- ASCII to and from EBCDIC
- remote transaction program datatypes to and from PL/SQL datatypes
- national language support for many languages

1.3 Terms

The following terms and definitions are used throughout this guide. Refer to Gateway Terminology for a more elaborate list of terms and definitions pertaining to the gateway, its components and functions.

Oracle Database

This is any Oracle database instance that communicates with the gateway for purposes of performing remote procedural calls to execute remote transaction programs (RTP). The Oracle database can be on the same system as the gateway or on a different system. If it is on a different system, then Oracle Net is required on both systems. Refer to Figure 1-2 for a view of the gateway architecture.

OLTP

Online Transaction Processor (OLTP) is any of a number of online transaction processors available from other vendors, including CICS Transaction Server for z/OS, IMS/TM, and z/OS

PGAU

Procedural Gateway Administration Utility (PGAU) is the tool that is used to define and generate PL/SQL Transaction Interface Packages (TIPs.) Refer to Chapter 2, "Procedural Gateway Administration Utility" in the *Oracle Database Gateway for APPC User's Guide* for more information about PGAU.

PG DD

Procedural Gateway Data Dictionary (PG DD) is a repository of remote host transaction (RHT) definitions and data definitions. PGAU accesses definitions in the Data Dictionary



(PG DD) when generating TIPs. The PG DD has datatype dependencies because it supports the PGAU and is not intended to be directly accessed by the customer. Refer to Appendix A, "Database Gateway for APPC Data Dictionary" in the *Oracle Database Gateway for APPC User's Guide* for a list of PG DD tables.

RPC

Remote Procedural Call (RPC) is a programming call that executes program logic on one system in response to a request from another system. Refer to Gateway Terminologyfor more information, and refer to Appendix C, "Gateway RPC Interface" in the *Oracle Database Gateway for APPC User's Guide* as well.

RTP

A remote transaction program (RTP) is a customer-written transaction, running under the control of an OLTP, which the user invokes remotely using a PL/SQL procedure. To execute a RTP through the gateway, you must use RPC to execute a PL/SQL program to call the gateway functions.

TIP

A Transaction Interface Package (TIP) is an Oracle PL/SQL package that exists between your application and the remote transaction program. TIP is a set of PL/SQL stored procedures that invoke the remote transaction program through the gateway. TIPs perform the conversion and reformatting of remote host data using PL/SQL and UTL RAW or UTL PG functions.

Figure 1-1 illustrates where the terminology discussed in the preceding sections apply within the gateway's architecture.

Oracle Microsoft Windows Database Transaction Gateway Remote Oracle Net **Procedure Calls** Interface Package PG DD **PGAU** Client **Data Dictionary** SNA or TCP/IP Mainframe **OLTP** Remote Transaction Program

Figure 1-1 Relationship of Gateway and Oracle Database on Windows



1.4 Architecture of the Gateway

The architecture of Oracle Database Gateway for APPC consists of several components:

- Oracle database
- The gateway

Oracle Database Gateway for APPC must be installed on a server that can run the required version of the operating system.

An OLTP

The OLTP must be accessible from the gateway using the SNA or TCP/IP communication protocol. Multiple Oracle database s can access the same gateway. A single system gateway installation can be configured to access more than one OLTP.

• For a gateway using TCP/IP support for IMS Connect: The only OLTP that is supported through TCP/IP is IMS through IMS Connect.

The OLTP must be accessible to the system using the TCP/IP protocol. Multiple Oracle database s can access the same gateway. A single-system gateway installation can be configured to access more than one OLTP. Multiple IMS can be accessed from an IMS Connect. If you have a number of IMS Connect systems available, then any of these may be connected to one or more IMS systems.

Figure 1-2 illustrates the architecture of Oracle Database Gateway for APPC using either SNA or TCP/IP, as described in the preceding section.




Figure 1-2 Gateway Architecture



1.5 Implementation of the Gateway

The basic structure of the gateway is the same whether your communications protocol is SNA or TCP/IP support for IMS Connect. The gateway has some of the same components as an Oracle database instance on Microsoft Windows. It has the following components:

- a home directory, similar to the one associated with an Oracle instance's ORACLE HOME environment variable;
- a system identifier, identified as sid or ORACLE SID;
- an initialization parameter file, similar to the Oracle database 's initsid.ora file.

The gateway does not have:

- control, redo log, or database files;
- the full set of subdirectories and ancillary files associated with an installed Oracle database.

Because the gateway has no background processes and does not need a management utility such as Oracle Enterprise Manager, you do not need to start the gateway product. Each Oracle database user session that accesses a particular gateway creates an independent process on Windows, which, in turn, runs the gateway server and executes either the SNA or TCP/IP functions to communicate with an OLTP.

1.6 Communication with the Gateway

All of the communication between the user or client program and the gateway is handled through a TIP which executes on an Oracle database . The TIP is a standard PL/SQL package that provides the following functions:

- declares the PL/SQL variables that can be exchanged with a RTP;
- calls the gateway packages that handle the communications for starting the conversation, exchanging data, and terminating the conversation;
- handles all datatype conversions between PL/SQL datatypes and the target program data types.

The PGAU, provided with the gateway, automatically generates the TIP specification.

The gateway is identified to the Oracle database using a database link. The database link is the same construct used to identify other Oracle databases. The functions in the gateway are referenced in PL/SQL as:

 $function_name@dblink_name$

1.7 Remote Procedural Call Functions

The Oracle Database Gateway for APPC provides a set of functions that are invoked by the client through remote procedural call (RPC). These functions direct the gateway to initiate, transfer data with, and terminate RTPs running under an OLTP on another system.



Table 1-1 lists the RPC functions and the correlating commands that are invoked in the gateway and remote host.

Table 1-1 RPC Functions and Commands in Oracle Database Gateway for APPC and Remote Host

Applications	Oracle TIP	Gateway	Remote Host
call tip_init	tip_init call pgainit@gateway	PGAINIT	Initiate program
call tip_main	tip_main call pgaxfer@gateway	PGAXFER	Exchange data
call tip_term	<pre>tip_term call pgaterm@gateway</pre>	PGATERM	Terminate program

1.7.1 Description of RPC Functions

The following sections describe how the RPC functions perform on gateways using SNA or TCP/IP communication protocols.

1.7.1.1 Remote Transaction Initiation

The TIP initiates a connection to the remote host system, using one of the gateway functions, PGAINIT.

When the communication protocol is SNA: PGAINIT provides, as input, the required SNA parameters to start a conversation with the target transaction program. These parameters are sent across the SNA network, which returns a conversation identifier to PGAINIT. Any future calls to the target program use the conversation identifier as an INPUT parameter.

When the communication protocol is TCP/IP: PGAINIT provides, as input, the required TCP/IP parameters. Use the pg4tcpmap tool to map the parameters. These parameters are sent across the TCP/IP network to start the conversation with the target transaction program, the TCP/IP network returns a socket file descriptor to PGAINIT. Future calls to the target program made by PGAXFER and PGATERM use the socket file descriptor as an input parameter.

Refer to Gateway Initialization Parameters for TCP/IP Communication Protocol in this guide, and to Chapter 6 in the *Oracle Database Gateway for APPC User's Guide*, for more information about the function and use of the pg4tcpmap tool.

1.7.1.2 Data Exchange

After the conversation is established, a database gateway function called PGAXFER can exchange data in the form of input and output variables. PGAXFER sends and receives buffers to and from the target transaction program. The gateway sees a buffer as only a RAW stream of bytes. The TIP that is residing in the Oracle database is responsible for converting the application's PL/SQL datatypes to RAW before sending the buffer to the gateway. It is also responsible for converting RAW to the PL/SQL datatypes before returning the results to the application.



1.7.1.3 Remote Transaction Termination

When communication with the remote program is complete, the gateway function PGATERM terminates the conversation between the gateway and the remote host.

When the communication protocol is SNA:, PGATERM uses the conversation identifier as an INPUT parameter to request conversation termination.

When the communication protocol is TCP/IP:, PGATERM uses the socket file descriptor for TCP/IP as an INPUT parameter to request conversation termination.

1.8 Transaction Types for Gateway Using SNA

The Oracle Database Gateway for APPC supports three types of transactions that read data from and write data to remote host systems:

one-shot

In a one-shot transaction, the application initializes the connection, exchanges data, and terminates the connection, all in a single call.

persistent

In a persistent transaction, multiple calls to exchange data with the remote transaction can be executed before terminating the conversation.

multiconversational

In a multiconversation transaction, the database gateway server can be used to exchange multiple records in one call to the RTP.

Refer to "Remote Host Transaction Types" in Chapter 4, "Client Application Development" of the *Oracle Database Gateway for APPC User's Guide* for more information about transaction types.

The following list demonstrates the power of the Oracle Database Gateway for APPC:

- You can initiate a CICS transaction on the mainframe to retrieve data from a VSAM file for a PC application.
- You can modify and monitor the operation of a remote process control computer.
- You can initiate an IMS/TM transaction that executes static SQL in DB2.
- You can initiate a CICS transaction that returns a large number of records in a single call.

1.9 Transaction Types for Gateway Using TCP/IP

The Oracle Database Gateway for APPC using TCP/IP for IMS Connect supports three types of transaction socket connections:

transaction socket

The socket connection lasts across a single transaction.

persistent socket

The socket connection lasts across multiple transactions.



nonpersistent socket

The socket connection lasts across a single exchange consisting of one input and one output.



Do not use the nonpersistent socket type if you plan on implementing conversational transactions because multiple connects and disconnects will occur.

Refer to the section about pg4tcpmap commands in Chapter 6 of the *Oracle Database Gateway for APPC User's Guide* and to Gateway Configuration Using TCP/IP Communication Protocol in this guide for more information about how to enter these parameters.

You can initiate an IMS/TM transaction that executes static SQL in DB2, this illustrates the power of the Oracle Database Gateway for APPC feature supporting TCP/IP for IMS Connect.



Release Information

The following topics provide information about this release of the Oracle Database Gateway for APPC:

- Product Set
- Changes and Enhancements
- Known Restrictions

2.1 Product Set

The following product components are included in the product installation media:

- Oracle Database Gateway for APPC, 12c Release 2 (12.2)
- Oracle Net, 12c Release 2 (12.2)

2.2 Changes and Enhancements

The following sections describe the changes and enhancements unique to the 11g release of the gateway:

- Gateway Password Encryption Tool
- Partial IPv6 Support

2.2.1 Gateway Password Encryption Tool

The Gateway Password Encryption tool (g4drpwd) has been replaced by a generic feature that is now part of Heterogeneous Services. Refer to Chapter 15, "Security Considerations" in Oracle Database Gateway Installation and Configuration Guide for Microsoft Windows for details.

2.2.2 Partial IPv6 Support

There is full IPv6 support between Oracle databases and the gateway but IPv6 is not yet supported between the gateway and IMS Connect.

2.3 Known Restrictions

The following sections list the known restrictions for the Oracle Database Gateway for APPC and PGAU.

2.3.1 Known Restrictions for the Gateway

The following restrictions are known to exist in this release of the Oracle Database Gateway for APPC.

Multibyte Character Sets Are Not Supported for Numeric Data and Clauses

The Oracle Database Gateway for APPC has supported multibyte character set data for COBOL PIC G datatypes since version 3.4. However, the non-numeric character data (such as \$, (,), +, -,.) that is allowed in DISPLAY datatypes and PIC 9 edit masks must still be specified in EBCDIC. The non-numeric character data is not subject to MBCS translation.

CICS Transactions Do Not Allow PF Key Emulation

When performing a CICS transaction using the Oracle Database Gateway for APPC, you cannot emulate CICS PF keys.

APPC PIP Data Is Not Supported

You cannot define and transmit APPC PIP data in this release of the Oracle Database Gateway for APPC.

Floating Point Data Type Conversion Is Not Supported

Oracle Database Gateway for APPC does not support floating point data type conversion.

Transaction Programs Are Responsible for All Data Compression and Decompression

The Oracle Database Gateway for APPC does not provide exits for compression and decompression facilities. All data exchanged between the gateway and the transaction must be in uncompressed format.

IBM VS COBOL II Compiler Desupported

The IBM VS COBOL II compiler has been desupported. However, the string "IBMVSCOBOLII" is still used as the value of the compiler name parameter to represent any COBOL compiler you choose to use. The value IBMVSCOBOLII should still be used and does not create a dependency on any specific version of the compiler.

2.3.2 Known Restrictions for PGAU

Restrictions with PGAU COBOL COPY REPLACE

When COBOL input to the PGAU DEFINE DATA statement contains a COPY REPLACE clause, only the first replacement is made.



3

System Requirements

The following topics describe the system requirements of the gateway.

- Hardware Requirements
- Software Requirements

3.1 Hardware Requirements

The hardware requirements for this release of the gateway on Microsoft Windows are described in the following sections.

3.1.1 Processor Requirements

Refer to the *Oracle Database Installation Guide for Microsoft Windows* and to the certification matrix on My Oracle Support for the most up-to-date list of certified hardware platforms and operating system version requirements to operate the gateway for your system. The My Oracle Support Web site can be found at:

https://support.oracle.com

The Oracle Database Gateway for APPC requires an Intel or 100% compatible personal computer based on a Pentium processor that can run Microsoft Windows 2000 and higher.

3.1.2 Memory Requirements

For most installations, Oracle recommends a minimum of 256 MB of real memory for the system running the Oracle Database Gateway for APPC.

Each concurrent use of the gateway requires a minimum of 10 MB.

The following factors affect the virtual memory requirements of the gateway server process:

- number of concurrent gateway connections opened by each user;
- number of data items being transferred between the gateway and the RTP;
- additional factors such as configured network buffer size;
- the Oracle Net protocol adapters that were included during the gateway installation.

3.1.3 Network Attachment Requirements

The gateway requires any network attachment supported by either the SNA Server for your platform or the TCP/IP Networking Facility for TCP/IP communication.

However, if you are using solely the new TCP/IP support for IMS Connect feature, you will not need an SNA package. The Windows operating system comes with TCP/IP installed, you will need to configure it.

3.1.4 Disk Space Requirements

The gateway disk space requirement is a minimum of 700 MB.

3.2 Software Requirements

The system software configuration described in these requirements is supported by Oracle, provided that the underlying system software products are supported by their respective vendors. Verify the latest support status with your system software vendors.

3.2.1 Operating System Requirements

Refer to the *Oracle Database Installation Guide for Microsoft Windows* and to the certification matrix on My Oracle Support for the most up-to-date list of certified operating system version requirements to operate the gateway for your Windows Intel system. The My Oracle Support Web site can be found at:

https://support.oracle.com

3.2.2 Communication Protocol Requirements

A Microsoft Host Integration Server 2000 is required, or IBM Communication Server V6.1.1 (or higher) for Windows. In this document, either of these communications servers will be referred to generically as SNA Server.



If you choose to use TCP/IP support for IMS Connect as your communications protocol, then you will not need to use an SNA Server. Your operating system comes with a TCP/IP protocol automatically installed. If you choose to use the TCP/IP protocol, you will need to configure it to work properly with the gateway then instructions for doing so are located in Gateway Configuration Using TCP/IP Communication Protocol.

3.2.3 Oracle Database Requirements

The Microsoft Windows platform requires that the Oracle database be up to date with the latest patch set for supported Oracle database releases.

3.2.4 Oracle Networking Product Requirements

Oracle Net is automatically installed on the system where the Oracle database is installed and on the system where the gateway is installed. Refer to Configuring Your Oracle Network in this guide for configuration information. Additionally, you may refer to the *Oracle Database Net Services Administrator's Guide*.



3.2.5 IBM Mainframe Requirements

In addition to the other software requirements of the gateway and your particular platform, the following list outlines other requirements necessary on the IBM mainframe:

OLTP for SNA

The OLTP must support mapped APPC conversations. If the OLTP transaction programs to be executed through the gateway perform database updates, then the APPC verbs CONFIRM, CONFIRMED, and SEND_ERR must be supported by the OLTP. These verbs implement APPC SYNCLEVEL 1.

All resources controlled by an OLTP that can be updated by transaction programs invoked through the gateway must be defined as recoverable resources to the OLTP and host system if COMMIT/ROLLBACK capability is required for those resources. For example, a VSAM file updated by a CICS transaction must be defined to CICS as a recoverable file for COMMIT/ROLLBACK to control the updates.

The gateway is compatible with all supported releases of SNA-enabled products such as CICS, IMS/TM, and z/OS.

Important: For a list of known restrictions, read the "Known Restrictions" sectionKnown Restrictions before proceeding with installation of the gateway.

OLTP for TCP/IP

IMS/TM: Release 7.1 or later is required, as well as any APARs (patches) listed in the IBM IMS Connect Guide and Reference.

IMS Connect: Release 1.2 or higher is required.



4

Installing the Gateway

The following topics describe how to install and configure the Oracle Database Gateway for APPC:

- · Before You Begin
- Planning to Upgrade or Migrate the Gateway
- Performing Preinstallation Procedures
- Installing the Gateway Software
- Using Windows User Account as Oracle Home User
- Installation Steps
- Removing Your Oracle Database Gateway for APPC

4.1 Before You Begin

Configuring an online transaction processor to allow access by the gateway requires actions on the OLTP and on certain components of the host operating system. Although no Oracle software is installed on the host system, access to, and some knowledge of the host system and the OLTP are required. Although the following topics include some information about host system and OLTP installation steps, you must ensure that you have the applicable OLTP and host system documentation available.

Some of the configuration actions on the OLTP might require you to restart the OLTP. In preparation for this, have your host system programmer or DBA review the instructions for your OLTP to allow for any necessary preparations.

To install and configure the gateway with a single Oracle database and a single OLTP, perform the procedures described in the following topics.



If your gateway uses the SNA communication protocol, then follow the instructions for installation and configuration in this chapter, in Configuring Your Oracle Network and in Gateway Configuration Using SNA Communication Protocol .

If your gateway uses the TCP/IP communication protocol, then follow the instructions for installation and configuration in this chapter, in Configuring Your Oracle Network and in Gateway Configuration Using TCP/IP Communication Protocol.

4.2 Planning to Upgrade or Migrate the Gateway

If you have an earlier version of the Oracle Database Gateway for APPC installed on your system, then you may be upgrading or migrating to the current release. A gateway upgrade represents a minor software upgrade within a release, (for example, moving from Release 9.0 to Release 9.2.0) a gateway migration represents a significant change from one version number to another, (for example, migrating from Release 9.0 to 10.2).

This section is only for customers who have a previous release of Oracle Database Gateway for APPC. If you have a previous gateway installation, then you will need to carry out specific tasks before you can install Oracle Database Gateway for APPC 12c Release 2 (12.2).

After reading this section, read Migration from Existing Gateways to determine the specific actions you must take to prepare for upgrade or migration of your gateway. If you are migrating to Oracle Database Gateway for APPC 12c Release 2 (12.2) from version 4.01 or earlier, then you will find specific material related to migration of the gateway in Migration from Existing Gateways.

If you are installing for the first time, then begin with "Performing Preinstallation Procedures".

4.2.1 Performing Pre-Upgrade Procedures

Perform the following steps to prepare for upgrading the Oracle Database Gateway for APPC to current versions:

- 1. Make backups of altered PGA shipped files.
- 2. Remove or rename any old gateway directories.

4.2.2 Upgrade and Migration Considerations

Upgrade considerations are as follows:

- PGAU control files from Gateway Release 8 or 9 are upward-compatible, and you
 do not need to change them.
- After upgrade, the PG DD contains all of its earlier entries without modification.
 New PGAU control information has been added along with some columns to support new features, but no customer entries are altered by the upgrade.
- All TIPs from Oracle Database Gateway for APPC Release 4.0.1 or earlier must be recompiled, due to changes in the following:
 - PL/SQL compatibility
 - gateway server RPC interface
 - UTL PG interface
- TCP/IP only: If you have existing TIPs that were generated previously on a
 gateway using the SNA communication protocol and you want to use the new
 TCP/IP feature, then the TIPs will have to be regenerated by PGAU with
 mandatory NLS_LANGUAGE and Side Profile Settings. Specify the appropriate ASCII
 character set in the DEFINE TRANSACTION command.



This is due to the fact that the gateway assumes that the appropriate user exit in IMS Connect is being used, which would translate between the appropriate ASCII and EBCDIC character sets.



Caution:

An upgraded PG Data Dictionary (PG DD) cannot be accessed by an earlier release of PGAU.

4.2.3 Restoration

If you want to restore a previous release of gateway, then you must restore the following components to their previous versions:

- PGAU
- PG DD
- gateway server

4.3 Performing Preinstallation Procedures

Before you install the gateway, perform the following preinstallation procedures:

- Ensure that your system meets all the hardware and software requirements specified in System Requirements.
- Ensure that your security requirements are met.
 - Refer to System Requirements for more information about the security requirements for connections and data access on your OLTP.
- Fill out the worksheet identifying unique parameter names needed to configure your system and your chosen communication protocol (either SNA or TCP/IP), which is located in Configuration Worksheet.
- Decide on an SID (system identifier) for your gateway. This SID is used in Configuring the GatewayConfiguring the Gateway.
 - The SID must be unique and must not be used by any other gateway or Oracle database on the system.
- SNA only: Your SNA package must be installed and configured before you can proceed
 with installation of the gateway. Ensure that your system can communicate with the OLTP
 using the SNA Server required for your platform. Refer to Configuring the SNA
 Communication Package on Windows for more information about setting up and
 configuring SNA for Windows.
- **TCP/IP only**: Your TCP/IP package must be installed and configured before you can proceed with installation of the gateway.
 - Ensure that your system can communicate with the OLTP using the TCP/IP communication package for your platform.

If you need general information about installing Oracle products and using the Oracle Universal Installer, then refer to the *Oracle Database Installation Guide for Microsoft Windows*

4.3.1 Gateway Installation Methods

You can install the gateway in either of the following ways:

- On the same system as the existing Oracle database but in a different directory.
 All tasks for this type of installation or upgrade are discussed in this section.
- 2. On a system different from a local Oracle database.
- 3. On the same system as the Oracle database, and in the same Oracle home directory. Note that in this case, the Oracle database and the gateway must be at the same release level.

4.4 Installing the Gateway Software

For general information about installing Oracle products and how to use the Oracle Universal Installer, refer to the *Oracle Database Installation Guide for Microsoft Windows* and perform all necessary tasks there first.

If your server release is different than your gateway release, then *do not* install the gateway in the same Oracle home directory as the Oracle database. This is required to isolate the gateway from the Oracle database upgrades that might cause incompatibilities if the gateway executables were relinked with later versions of the Oracle database libraries.

4.5 Using Windows User Account as Oracle Home User

With Windows, you log in as a user with Administrator privileges to install the Oracle Database software. You can also specify an Oracle Home User (based on a low-privileged, non-administrative user account) during installation.

The following are the Windows User Accounts:

- Windows Local User account
- Windows Domain User account
- Windows Managed Services Account (MSA)
- Windows Built-in Account



"Using Oracle Home User on Windows" in *Oracle Database Platform Guide* for *Microsoft Windows*

4.6 Installation Steps

If you wish to install the gateway in the same Oracle home as the Oracle database, then the release number of both products must be the same.



4.6.1 Step 1: Log On to Windows System

Log on to your Windows system as a member of the Administrators group. If you are not currently a DBA user, then contact your system administrator to create a DBA login user ID. Refer to the *Oracle Database Installation Guide for Microsoft Windows* for login information.

4.6.2 Step 2: Ensure Minimum Amount of Disk Space

If you are installing the gateway for the first time, then ensure that there is enough space on the disk where the gateway will reside, as specified in "Disk Space Requirements".

4.6.3 Step 3: Stop All Oracle Services

Before beginning the gateway installation process, you must stop all Oracle services that are currently running. Follow these steps:

- 1. Click Start, then Settings, then Control Panel.
- 2. Select **Services**. A list of all Windows services appears.
- 3. Select an Oracle service (those services begin with Oracle).
- 4. Click Stop.
- 5. Continue to select and stop Oracle services until all active Oracle services are stopped.

4.6.4 Step 4: Insert the Gateway Product Installation Media

Verify that the drive is assigned to the logical drive you selected and that you can access files on the installation media.



The installation steps that follow assume that the installation media location is mapped to the D: drive.

The installation media package contains the Oracle Database Gateway for APPC and the Oracle Universal Installer.

4.6.5 Step 5: Start the Oracle Universal Installer

To start the Oracle Universal Installer, run setup.exe:

- 1. From the Start Menu, select Run.
- 2. Enter the path of the executable file name. For example:

D:\Disk1\setup.exe



4.6.6 Step 6: Step Through the Oracle Universal Installer



Oracle Universal Installer automatically installs the Oracle-supplied version of the Java Runtime Environment (JRE). This version is required to run the Oracle Universal Installer and several Oracle assistants. Do not modify the JRE except by using a patch provided by Oracle Support Services. The Oracle Universal Installer also installs JDK.

Oracle Universal Installer is a menu-driven utility that guides you through installing the gateway by prompting you with action items. The action items and the sequence in which they appear depend on your platform.

The following section describes how to use the Oracle Universal Installer to install the gateway on your platform.

4.6.6.1 Oracle Universal Installer on Windows Platforms

Use Table 4-1 as a guide to step through the Oracle Universal Installer. At each prompt from the Oracle Universal Installer, perform the actions described in the Response column of the table to install the gateway on your Windows platform.

Table 4-1 The Oracle Universal Installer: Steps for Installing Oracle Database Gateway for APPC

Prompt	Response
Oracle Universal Installer: Welcome	Click Next
Oracle Universal Installer: Specify	a. Specify the name of the installation.
Home Details	Specify the full path where you want to install the product
	Click Next
Oracle Universal Installer: Available	a. Deselect the checked products
Product Components	b. Select Oracle Database Gateway 12.2, open up this row
	c. Select Oracle Database Gateway for APPC 12.2. (Note that you may also choose to select other products to install besides the Oracle Database Gateway for APPC).
	d. Click Next
Oracle Universal Installer: Network Software	Specify your network package and click Next
Oracle Universal Installer: Summary	Click Install
Oracle Net Configuration Assistance: Welcome	Click Next
Oracle Net Configuration Assistance: Listener Configuration, Listener Name	Specify the name of Listener you want to create and click Next



Table 4-1 (Cont.) The Oracle Universal Installer: Steps for Installing Oracle Database Gateway for APPC

Prompt	Response
Oracle Net Configuration Assistance: Listener Configuration, Select Protocols	· · · · · · · · · · · · · · · · · · ·
Oracle Net Configuration Assistance: Listener Configuration, TCP/IP Protocol	Specify a port number and click Next
Oracle Net Configuration Assistance:Listener Configuration, More Listeners?	Click No and then click Next
Oracle Net Configuration Assistance: Listener Configuration Done	Click Next
Oracle net Configuration Assistance: Naming Methods Configuration	Click No and then click Next
Oracle Net Configuration Assistance:Done	Click Yes
Oracle Universal Installer: End of Installation	Click Finish
Exit	Click Exit

Your gateway is now installed.

When the Oracle Universal Installer confirms that the installation is complete, verify that the installation procedure was successful. To do this, read the contents of the installation log file, which is located in the $C:\Program\ Files\Oracle\Inventory\logs\ directory.$

The default file name is InstallActionsYYYY-MM-DD_HH-mm-SS-AM/PM.log, where:

YYYY is year;

MM is month

DD is day

HH is hour

mm is minute

SS is seconds

AM/PM is daytime or evening

Each of these variables in the log file name represents the date and time the product was installed.



Print the contents of the <code>%ORACLE_HOME%\dg4appc\doc\README.doc</code> file and read the entire document, it contains important information about the installation. After reading the <code>README.doc</code> file, proceed with the configuration of the gateway.



4.7 Removing Your Oracle Database Gateway for APPC

The following topics describe how to remove Oracle Database Gateway from an Oracle home directory. It contains information about the following topics:

- About the Deinstallation Tool
- Removing Oracle Software

4.7.1 About the Deinstallation Tool

The Deinstallation Tool (deinstall) is available in the installation media before installation, and is available in Oracle home directories after installation. It is located in ORACLE HOME\deinstall.

The deinstall command stops Oracle software, and removes Oracle software and configuration files on the operating system.

The script uses the following syntax, where variable content is indicated by italics:

```
deinstall -home complete path of Oracle home [-silent] [-checkonly] [-local] [-paramfile complete path of input parameter property file] [-params namel=value name2=value . . .] [-o complete path of directory for saving files] [-help | -h]
```

The options are:

-silent

Use this flag to run the command in noninteractive mode. This option requires a properties file that contains the configuration values for the Oracle home that is being deinstalled or deconfigured.

To create a properties file and provide the required parameters, see the template file <code>deinstall.rsp.tmpl</code>, located in the response folder. If you prefer, instead of using the template file, you can generate a properties file by using the <code>-checkonly</code> option to have deconfig discover information from the Oracle home that you want to deinstall and deconfigure. The tool will generate the properties file, which you can then use with the <code>-silent</code> option.

· -checkonly

Use this flag to check the status of the Oracle software home configuration. Running the command with the -checkonly flag does not remove the Oracle configuration.

• -local

Use this flag on a multinode environment to deconfigure Oracle software in a cluster.

When you run deconfig with this flag, it deconfigures and deinstalls the Oracle software on the local node (the node where deconfig is run). On remote nodes, it deconfigures Oracle software, but does not deinstall the Oracle software.

• -paramfile complete path of input parameter property file

Use this flag to run deconfig with a parameter file in a location other than the default. When you use this flag, provide the complete path where the parameter file is located.



The default location of the parameter file depends on the location of deconfig:

- From the installation media or stage location: ORACLE HOME\response
- From an unzipped archive file from Oracle Technology Network:
 ziplocation\response
- After installation from the installed Oracle home: ORACLE HOME\deinstall\response
- -params [name1=value name 2=value name3=value . . .]

Use this flag with a parameter file to override one or more values that you want to change in a parameter file you have already created.

-o complete path of directory for saving files

Use this flag to provide a path other than the default location where the properties file is saved. The default location is \response\deinstall.rsp.tmpl.

The default location of the parameter file depends on the location of deconfig:

- From the installation media or stage location before installation: ORACLE HOME\
- From an unzipped archive file from Oracle Technology Network: \ziplocation\response\
- After installation from the installed Oracle home: ORACLE HOME/deinstall/response
- -help | -h

Use the help option (-help or -h) to obtain additional information about the optional flags

4.7.2 Removing Oracle Software

Complete the following procedure to remove Oracle software:

- 1. Log in as a member of the Administrators group.
- 2. Run the deinstall command, providing information about the Oracle System Identifier (SID), when prompted.



Configuring Your Oracle Network

The instructions in this section describe how to configure the network whether your gateway is using the SNA or TCP/IP communication protocol.

The gateway must be defined to the Oracle Net Listener, and a service name must be defined for accessing the gateway. To do this, perform the following steps:

- 1. Add an entry for the gateway to the listener.ora file:
 - If you are using SNA:

```
(SID_DESC=
        (SID_NAME=PGA)
        (ORACLE_HOME= C:\oracle\pga\12.2)
        (PROGRAM=pg4asrv)
)
```

where: C:\oracle\pga12.2 is your gateway Oracle home, and PGA is the gateway SID name.

Or, if you are using TCP/IP:

```
(SID_DESC=
    (SID_NAME=PGA)
    (ORACLE_HOME= C:\oracle\pga\12.2)
    (PROGRAM=pg4t4ic)
)
```

where: C:\oracle\pga12.2 is your gateway Oracle home, and PGA is the gateway SID name.

2. Add a service name for the gateway to the tnsnames.ora file on the system where your Oracle database is located. The service name is specified in the USING parameter of the database link defined for accessing the gateway from the Oracle database. For example, if you are using the IPC protocol adapter and your gateway service_name is PGA, then add the following entry to tnsnames.ora:

In this example, key is the IPC key defined in the listener.ora file for the IPC protocol. You can use the IPC protocol only if the Oracle database and the gateway are on the same system.

If you are using the TCP/IP protocol adapter and if your gateway <code>service_name</code> is PGA, then add the following entry to <code>tnsnames.ora</code>:



```
(CONNECT_DATA = (SERVICE_NAME=PGA))
(HS=)
```

In this example, <code>port</code> is the TCP port defined in the <code>listener.ora</code> file for the TCP protocol, and <code>gateway</code> is the TCP/IP host name of the system where the gateway is located.

Note:

Under the following circumstances:

- If your gateway and Oracle database are not on the same system,
- or, if the gateway and the Oracle database are on the same system but the Oracle database Listener is different than the gateway listener,

then you must define the Oracle database to PGAU by adding a service name to tnsnames.ora on the system where your gateway resides. For example:

In this example,

- port is the TCP port defined in the Oracle database listener.ora for the TCP protocol;
- ora_srv is the TCP/IP host name of the system where the Oracle database resides; and
- ora server is the service name of the Oracle database.

Make sure to start your defined listeners. Refer to the *Oracle Database Net Services Administrator's Guide* for more information about configuring the network.

To see a sample listener.ora file refer to "Sample listener.ora File for a Gateway Using SNA" and "Sample tnsnames.ora File for a Gateway Using SNA" in Gateway Initialization Parameters for SNA Protocol (if your communication protocol is SNA).

To see a sample listener.ora file refer to "Sample listener.ora File for a Gateway Using TCP/IP" and "Sample tnsnames.ora File for a Gateway Using TCP/IP" in Gateway Initialization Parameters for TCP/IP Communication Protocol (if your communication protocol is TCP/IP).



Example 5-1 Proceed with Configuring Your Communication Package for the Gateway

- **If your communication protocol is SNA**, you must now configure the SNA Server profiles for APPC connections.
 - Proceed to Configuring the SNA Communication Package on Windows
- If your communication protocol is TCP/IP, proceed to Configuring the OLTP.



6

Configuring the SNA Communication Package on Windows

The Oracle Database Gateway for APPC uses the SNA Advanced Program to Program Communication (APPC/LU6.2) protocol to communicate with an OLTP.

APPC support on Microsoft Windows can be provided by using either of the following tools:

- Microsoft Host Integration Server 2000 (HIS), or
- IBM Communications Server v6.1.1 (or higher).

Read the following topics to learn how to configure the SNA Server on a Windows system to run the Oracle Database Gateway for APPC, using either a Microsoft Host Integration Server or IBM Communications Server.

- Using SNA Security Validation
- Processing Inbound Connections
- Configuring Your Microsoft Host Integration Server
- Creating SNA Server Definitions on Microsoft Host Integration Server
- · Configuring an IBM Communications Server
- Creating IBM Communications Server Definitions for the Gateway
- Testing the Connection
- Resume Configuration of the Gateway

6.1 Using SNA Security Validation

When a Remote Procedure Call (RPC) request to start a remote transaction program (RTP) is received by the gateway, the gateway attempts to start an APPC conversation with the OLTP. Before the conversation can begin, a session must start between the Windows Logical Unit (LU) and the OLTP LU.

SNA and its various access method implementations (including HIS and IBM Communication Server and VTAM) provide security validation at session initiation time, allowing each LU to authenticate its partner. This validation is carried out entirely by network software before the gateway and OLTP application programs begin their conversation and process conversation-level security data. If session-level security is used, then correct password information must be established in the Windows SNA Server definitions and in similar parameter structures in the OLTP to be accessed. Refer to suitable communications software product documentation for detailed information about this subject.

6.2 Processing Inbound Connections

Many OLTPs provide options for manipulating the security conduct of an inbound (client) APPC session request. Refer to suitable OLTP documentation for detailed information about this topic.

Note that for CICS, one security option is not supported by the gateway:

• ATTACHSEC=PERSISTENT, specified on the CICS CONNECTION definition, requires capability that is not yet available in the gateway.

However, ATTACHSEC=LOCAL, ATTACHSEC=IDENTIFY, ATTACHSEC=VERIFY, and ATTACHSEC=MIXIDPE are fully supported by the gateway.

6.3 Configuring Your Microsoft Host Integration Server

The following sections discuss general information about the SNA Server and how to configure a Microsoft Host Integration Server.



If you are using the IBM Communication Server to configure your Windows system for the gateway, then proceed to Configuring an IBM Communications Server.

Note:

Although the Microsoft Host Integration Server has replaced the Microsoft SNA Server Manager, configuration of the communication package remains the same.

This means that the following steps shown for configuring the Microsoft SNA Server Manager also apply to the Microsoft Host Integration Server. The graphic windows you will actually see during configuration will be labelled as "Microsoft Host Integration Server" windows, rather than "SNA Server Manager".

6.3.1 Independent Versus Dependent LUs

Oracle recommends independent LUs for the Oracle Database Gateway for APPC because they support multiple parallel sessions or conversations. This means that multiple Oracle client applications can be active simultaneously with the same OLTP through the independent LU.

Dependent LUs support only a single active session. The CP (Control Point for the Node, which is SNA Server for Windows in this case) queues additional conversation requests from the gateway server behind an already active conversation. In other words, conversations are single-threaded for dependent LUs.

If a dependent LU is correctly defined, then no alterations to the Oracle Database Gateway for APPC configuration are needed, nor should any changes be needed to the host transaction or how the OLTP is started.

The operational impact of dependent LUs is that the first client application can initiate a conversation through the database gateway with the OLTP. While that transaction is active (which could be seconds to minutes to hours, depending on how the client application and transaction are designed), any other client application initiating a



conversation with the same OLTP instance appears to stop responding as it waits behind the previous conversation.

If a production application really uses only a single conversation or transaction at any one time, then there should be no impact.

However, additional concurrent conversations or transactions might be required for testing or for other application development. Each requires that additional dependent LUs be defined on the remote host, plus additional SNA Server configuration entries, which define the additional dependent LUs on the Windows system. The TIP that initiates the conversation must specify the different Partner LU through a different Side Information Profile or by overriding the LU name. Refer to PGAU DEFINE TRANSACTION, SIDEPROFILE, and LUNAME parameters in Chapter 2, "Procedural Gateway Administration Utility," in the *Oracle Database Gateway for APPC User's Guide*.

6.3.2 Location of Sample SNA Server Definitions

The <code>%ORACLE_HOME%\dg4appc\sna</code> subdirectory contains a sample set of gateway SNA Server definitions created with the <code>SNACFG</code> command. The <code>snacfg.ctl</code> file contains sample definitions for SNA Server.

Before building the SNA Server definitions, examine the snacfg.ctl file to determine the definitions needed, their contents, and their inter-relationships. The file format is text-oriented, and each field of each definition is clearly labelled. You can print a copy of the file to use while working with your definitions in a Microsoft Host Integration Server (formerly SNA Server Manager) session.

6.3.3 HIS Definition Types

Several types of SNA Server definitions are relevant to gateway APPC/LU6.2 operation. Each definition can be created and edited using a corresponding Microsoft Host Integration Server (formerly SNA Server Manager) menu.

The definitions relevant to the gateway are presented here in hierarchical order. Those definition types that are lowest in the hierarchy are discussed first. This matches the logical sequence in which to create the definitions.

Refer to the Windows HIS online documentation for a complete discussion of HIS definitions. This section provides an overview of HIS definitions in relation to the Oracle Database Gateway for APPC.

6.3.4 Methods of Creating SNA Server Definitions for the Gateway

HIS definitions can be created and modified in two ways:

 You can create the definitions using menus in the Microsoft Host Integration Server (formerly SNA Server Manager).

Using the Microsoft Host Integration Server is the recommended method for creating the definitions. You should be able to accept most of the defaults. The default values assigned to many of the fields in a new set of definitions are acceptable to the gateway.

Step through the tasks for creating SNA Server definitions in Creating SNA Server Definitions on Microsoft Host Integration Server Creating SNA Server Definitions on Microsoft Host Integration Server .



 Alternatively, you can install the definitions directly on your system using the SNACFG command.

For information on using the SNACFG command, refer to your vendor documentation.

If you use the SNACFG command method, then you must use Microsoft Host Integration Server (formerly SNA Server Manager) to review and modify the installed definitions. Because of configuration and naming differences, it is unlikely that they will work without modification.

Maintenance of SNA definitions is normally done by a user with Administrator authority. The following information is intended for the person creating SNA definitions for the gateway. You should have some knowledge of SNA before reading the following sections.

6.4 Creating SNA Server Definitions on Microsoft Host Integration Server

This section describes the process of creating your SNA definitions in the Microsoft Host Integration Server (formerly called the SNA Server Manager). All of the tasks described in this section are performed from within the Microsoft Host Integration Server.

6.4.1 Server Selection

Select the appropriate folder to ensure that definitions created are for that server. When HIS Manager is started, a dialog box appears.

Select the Servers folder under your local system and select the local SNA Server. From a list of services for that server, select the SNA Service.

6.4.2 Link Service Definition

You must install and configure a link service for SNA Server to use the network adapter installed in your workstation, as follows:

- 1. From the Insert menu, select Link Service.
- From the Insert Link Service dialog box, select the Link Service you want to use from the selection list and click Add. For example, select DLC 802.2 Link Service and click Add.

Now, the **Link Service Properties** dialog box is displayed. Note that the contents of this dialog box vary depending on which link service was selected. In this example, the **DLC 802.2 Link Service Properties** dialog box is used.

Select the suitable network adapter from the Adapter drop-down menu and click **OK**. In the **Insert Link Service** dialog box, click **Finish**. The system now updates your network bindings.

6.4.3 Connection Definition

To create a connection definition, perform the following steps:



- You must create a connection definition to define the devices which HIS uses to perform SNA communication. From the Insert menu, select Connection. The Connection Properties dialog box appears.
- 2. Select the **General** tab. Enter a connection name. This is the name used by HIS to name the connection. This example names the connection <code>TOKEN1</code>. From the Link Service dropdown menu, select a link service for the connection. All other settings can be left set to their default values.
- Select the Address tab in the Connection Properties box. Enter the Remote Network Address and the Remote SAP Address.
- 4. Select the **System Identification** tab. Under Local Node Name, enter the **Network Name**, **Control Point Name**, and **Local Node ID**.
- 5. Under Remote Node Name, enter the **Network Name**, **Control Point Name**, and optionally, the **Remote Node ID**. The XID Type should be set to Format 3.
- 6. Next, select the **DLC** tab in the **Connection Properties** box. In this example, the **802.2 DLC** (Token Ring) is being used. For the **802.2 DLC**, all of the defaults are usually acceptable. If you need to change any values, then do so now.
- 7. Now, all the connection properties are set. Click **OK** to continue.

6.4.4 Local LU Definition

You must create a local logical unit (LU) definition. The local LU definition describes the SNA LU through which the gateway communicates with OLTP systems. Perform the following steps to create a local LU definition:

- From the Insert menu, select Local APPC LU. The Local LU Properties dialog box appears.
- 2. Select the **General** tab. Enter the **LU Alias**, **Network Name**, and **LU Name**. Ensure that the **APPC SyncPoint Support** box is not checked.
- Select Advanced tab of the Local APPC LU Properties box. Check the Member of Default Outgoing Local APPC LU Pool check box. Set the LU 6.2 Type to Independent to allow parallel sessions.
- 4. Now, the Local LU properties are all set. Click **OK** to continue.

6.4.5 Mode Definition

This definition describes an SNA mode entry to be used when establishing sessions between LUs. The mode defined here must match a mode defined on the target system. Perform the following steps to create a mode definition:

- From the Insert menu, select APPC Mode Definition. The APPC Mode Properties dialog box appears.
- Select the General tab. Enter the Mode Name. The mode name that you specify must be
 defined to the OLTP communications software. Choose the mode name in addition to
 other mode parameters after consulting the person responsible for configuring the OLTP
 communications software.
- 3. Next, select the Limits tab. Enter the Parallel Session Limit, Minimum Contention Winner Limit, Partner Min Contention Winner Limit, and Automatic Activation Limit values.



- 4. The Parallel Session limit determines the maximum number of concurrent conversations allowed between the gateway instance and the OLTP. This equates to the maximum number of concurrently active RTP calls through the gateway instance.
- Now, select the Characteristics tab. Enter the Pacing Send Count, Pacing Receive Count, Max Send RU Size, and Max Receive RU Size. For optimal performance, check the High Priority Mode check box.
 - The pacing and RU size parameters are performance-related and should be tuned to suit your application. For most installations, the values set in the example are sufficient.
- **6.** After you finish entering the values called for in this box, all the APPC mode properties will be set. Click **OK** at the bottom of the box to continue.

6.4.6 Remote LU Definition

This definition describes the SNA LU of the OLTP system with which the gateway communicates. You must create a remote LU definition for the remote OLTP system. Determine the link with which to associate the LU (in the example, it is <code>TOKEN1</code>). Perform the following steps to create a remote LU definition:

- From the Insert menu, select APPC Remote LU. The Remote APPC LU Properties dialog box appears.
- Select the General tab. Use the Connection drop-down menu to select the connection used to access this LU. Enter the LU Alias, Network Name, LU Name, and Uninterpreted LU Name.
 - You should contact the person responsible for your SNA network to determine the correct LU and network names. Note that you can use the LU Alias to define a name known only to SNA Server, and that name can remain the same even if the remote LU name changes. This helps to reduce the amount of maintenance required when network changes occur.
- Now, select the Options tab. Check the Supports Parallel Sessions check box.
 Use the Implicit Incoming Mode drop-down menu to select the mode. Set any
 security options you need.
- 4. Once you have filled in the suitable values in the **Remote APPC LU Properties** box, the APPC LU properties will be set. Click **OK** to continue.

6.4.7 CPI-C Symbolic Destination Name

When the Local and Remote Partner definitions and Mode definitions have been created, you can create CPI-C Symbolic Destination Names, also called side information. The side information is used to identify target OLTP systems to be accessed through the gateway.

- From the Insert menu, select APPC CPIC Symbolic Name. The CPIC Name Properties dialog box appears.
- 2. Select the **General** tab. Enter a **Name** for the side information. From the Mode Name drop-down list, select the suitable mode.
- Now, select the Partner Information tab. Select Application TP and enter the TP name. If you plan to define one CPI-C Symbolic Destination Name for accessing



multiple transaction programs at an OLTP, then you can enter a dummy TP Name at this time. The TP Name is overridden by the gateway at run time.

Enter the Partner LU Name Alias.

4. Click **OK** to save the side information.

Configuration of the Microsoft Host Integration Server is now complete. Proceed to "Testing the Connection".

6.5 Configuring an IBM Communications Server

If you are using IBM Communications Server as your SNA Server, then read the following sections to learn how to configure it to communicate with the Oracle Database Gateway for APPC.

6.5.1 Independent And Dependent LUs

Oracle recommends independent LUs for the Oracle Database Gateway for APPC because they support multiple parallel sessions or conversations. This means that multiple Oracle client applications can be active simultaneously with the same OLTP through the independent LU.

Dependent LUs support only a single active session. The CP (Control Point for the node, which is IBM Communications Server, in this case) queues additional conversation requests from the gateway server behind an already active conversation. In other words, conversations are single-threaded for dependent LUs.

If a gateway LU is correctly defined, then no alterations to the Oracle Database Gateway for APPC configuration are needed, nor should any changes be needed to the gateway server.

The operational impact of dependent LUs is that the first client application can initiate a conversation through the database gateway with the gateway server. While that transaction is active (which could be seconds to minutes to hours, depending on how the client application and transaction are designed), any other client application initiating a session with the same gateway server appears to stop responding as it waits behind the previous session.

If a production application really uses only a single conversation at any one time, then there should be no impact.

However, additional concurrent conversations might be required for testing or for other application development. Each requires that additional dependent LUs be defined on the remote host, plus additional IBM Communication Server configuration entries, which define the additional dependent LUs on the host Windows system.

Additional side information profiles should be defined to use the new dependent LUs. New gateway instances should be created and configured to use these new side information profiles.

Refer to PGAU DEFINE TRANSACTION, SIDEPROFILE, and LUNAME parameters in Chapter 2, "Procedural Gateway Administration Utility," in the *Oracle Database Gateway for APPC User's Guide*.



6.5.2 Definition Types

Several types of IBM Communications Server definitions are relevant to gateway APPC/LU6.2 operation. Each definition can be created and edited using a corresponding SNA Node Configuration menu.

The definitions relevant to the gateway are presented here in hierarchical order. Those definition types that are lowest in the hierarchy are discussed first. This matches the logical sequence in which to create the definitions.

Refer to the IBM Communications Server online documentation for a complete discussion of IBM Communications Server definitions. This section provides an overview of IBM Communications Server definitions in relation to the Oracle Database Gateway for APPC.

6.6 Creating IBM Communications Server Definitions for the Gateway

IBM Communications Server definitions are created using the SNA Node Configuration tool, while the actual operation of the server is done using the SNA Node Operations tool, both of which are provided with IBM Communications Server.

Maintenance of SNA definitions is normally done by a user with Administrator privileges.

The following sections describe the process of creating your SNA definitions for IBM Communications Server using the SNA Node Configuration tool. All the tasks described in this section are performed within SNA Node Configuration.

6.6.1 Creating the Configuration

SNA Node Configuration will first ask you if you are creating a new configuration or loading an existing configuration. These tasks are based on the assumption that a new configuration is being created.

SNA Node Configuration will next prompt you for a configuration scenario.

6.6.2 Creating the Node

Each SNA Server must have a control point defined. This is typically called the Node definition. To define the node:

- Click Node.
- 2. Click Create.
- In the Define the Node dialog box, select the Basic tab. Enter the Control Point, Local Node ID, and Node Type information.

You can select **Advanced** tab options, depending on your SNA network configuration.

4. Click OK.



6.6.3 Creating Devices

Configure Communication Devices next. Follow these instructions:

- Click Devices.
- 2. Click Create.

6.6.4 Choosing the Device Type

Select the type of device to use for communication. The LAN type is typical for either Ethernet or Token Ring attached network devices.

6.6.5 Configuring a LAN Device

Configure a LAN device next. Follow these instructions:

- Select the Basic tab. Select the adapter to use and the Local SAP.
 The other tabs provide options on network tuning parameters.
- Click OK.

6.6.6 Creating Peer Connections

Configure Peer Connections next. Follow these instructions:

- Click Peer Connections.
- 2. Click Create.

6.6.7 Defining the Link Station

Define the Link Station next. Follow these instructions:

- 1. In the **Basic** tab, enter a Link Station name for this connection.
- 2. Choose the device for the connection.
- 3. Enter the Destination address and Remote SAP.

6.6.8 Defining the Adjacent Node

Define the Adjacent Node next. Follow these instructions:

- Select the Adjacent Node tab.
- Enter the Adjacent CP name of the remote system and pick its CP type. You may have to choose a different transmission group (TG) than the default. Consult your SNA network administrator for details.

Other tabs provide options on tuning and reactivation.

Click OK.



6.6.9 Creating Local LUs

Create Local LUs for this node next. Follow these instructions:

- Click Local LU 6.2 LUs.
- 2. Click Create.

6.6.10 Defining Local LUs

Define Local LUs next. Follow these instructions:

- 1. In the **Basic** tab, enter the name of the Local LU, and, optionally, an alias. The name must match the Local LU definition of the remote host for this node.
 - You can examine the other tab for synchronization support and for LU session limits.
- 2. Click OK.

6.6.11 Creating Partner LUs

Create remote Partner LUs next. Follow these instructions:

- 1. Click Partner LU 6.2 LUs.
- 2. Click Create.

6.6.12 Defining Partner LUs

Define Partner LUs next. Follow these instructions:

- In the Basic tab, enter the name of the Remote or Partner LU, and, optionally, an alias.
- 2. Select the Fully Qualified CP from the Existing list.

You can examine the other tab for logical record limits and security support.

3. Click OK.

6.6.13 Creating the CPI-C Side Information Profile

Next, define the CPI-C profile that will be used to create the gateway. Follow these instructions:

- 1. Click the CPI-C Side Information Definitions.
- 2. Click Create.

6.7 Testing the Connection

Before proceeding with the gateway configuration tasks, ensure that your connection is working. You can do this by using the Microsoft Host Integration Server (SNA Server Manager).



Figure 6-1 shows the relationship between SNA Server definitions and the VTAM definitions on the host.




Figure 6-1 Relationship Between SNA Server Definitions and Host VTAM

6.8 Resume Configuration of the Gateway

When you have finished configuring the SNA Server for your Windows system, proceed to Configuring the OLTP to continue configuring the network.

7

Configuring the OLTP

The following sections detail how to configure the OLTP.

- If your communications protocol is SNA: proceed to Configuring the OLTP for Your SNA EnvironmentConfiguring the OLTP for Your SNA Environment.
- If your communications protocol is TCP/IP: proceed to Configuring the OLTP for Your TCP/IP EnvironmentConfiguring the OLTP for Your TCP/IP Environment.



On a gateway using TCP/IP support for IMS Connect, you must specify EDIT=ULC in the IMS TRANSACT macro if you need input case sensitivity. When using SNA support, you need not specify EDIT=ULC in the IMS TRANSACT macro.

7.1 Configuring the OLTP for Your SNA Environment

The steps for configuring your OLTP to communicate with the Oracle Database Gateway for APPC vary, depending on which OLTP you are using and on which platform the OLTP is running. CICS Transaction Server for z/OS, IMS/TM, APPC/MVS, and z/OS are the currently supported OLTPs. Choose the instructions suitable to your OLTP from the following sections:

- "Configuring CICS Transaction Server for z/OS"
- "Configuring IMS/TM"
- "Configuring APPC/MVS"

Note:

You need only perform the configuration steps for an OLTP if this is a first-time configuration for that OLTP.

Configuring CICS Transaction Server for z/OS

If your OLTP is CICS Transaction Server for z/OS, then perform the following steps to configure it for communication with the gateway:

- 1. Configure MVS VTAM for the SNA Server that will make the APPC connection to your system. At least one independent LU must be available to the gateway.
- Check the VTAM logmode table used by the CICS Transaction Server for z/OS. (The
 table name is specified in the MODETAB parameter in the VTAM APPL definition for CICS.)
 Ensure that an entry exists for APPC sessions with parallel session and sync-level
 support.

The <code>oraplu62.asm</code> file in the <code>%ORACLE_HOME%\dg4appc\sna</code> directory contains a sample mode entry, including comments that indicate the required values in the mode entry.

- 3. Using your file transfer facility, transfer the following files from the <code>%ORACLE_HOME%</code>
 \dg4appc\demo\CICS directory to the z/OS system on which you run CICS
 Transaction Server for z/OS:
 - dfhcsdup.jcl JCL to run the CICS DFHCSDUP utility
 - pgaflip.asm assembler source for the CICS FLIP transaction
 - pgaflip.jcl JCL to assemble and linkedit the CICS FLIP transaction
- 4. Using the comments in the dfhcsdup.jcl file, tailor the JCL and input statements to match your system setup, and submit it for batch execution. Performing this step updates your Transaction Server for z/OS system definitions.
- 5. Using the instructions in the pgaflip.jcl file comments, tailor the JCL to match your system setup, and submit it for batch execution. Performing this step assembles and linkedits the pgaflip.asm file into a load module library accessible to your Transaction Server for z/OS through the DFHRPL DD statement in the CICS startup procedure.
- **6.** Log on to your CICS Transaction Server for z/OS and enter the following transaction:

```
CEDA INSTALL GROUP (ORAPGA)
```

This transaction installs the CICS connection and session definitions for APPC communication with the gateway on Windows. It also installs definitions for the sample CICS programs and transactions provided with the gateway.

Your CICS Transaction Server for z/OS configuration is now complete.

Configuring IMS/TM

If your OLTP is IMS/TM, then perform the following steps to configure IMS/TM and z/OS for communication with the gateway:

- 1. Configure the IMS system for use with APPC.
- 2. Configure MVS VTAM for the SNA APPC connection to Windows. At least one independent LU must be available for use by the gateway, unless you are using the IMS LU6.1 Adapter for LU6.2 applications. In this case, you must have one dependent LU defined for each concurrent session. For example, if you want to support 10 concurrent sessions, then you must have 10 dependent LUs defined.
- 3. Check the VTAM logmode table used by IMS/TM. The table name is specified by the MODETAB parameter in the VTAM APPL definition.
 - For APPC/IMS, ensure that an entry exists for APPC sessions with sync-level support and parallel session support. The $\tt oralu62.asm$ and $\tt oraplu62.asm$ files in the $\tt \#ORACLE_HOME\$ \dg4appc\sna}$ directory contain sample mode entries for single session and parallel session support, respectively. The samples include comments that indicate the required values in the mode entries.
- 4. Using your file transfer facility, transfer the following files from the <code>%ORACLE_HOME%</code> \dg4appc\demo\IMS directory to the z/OS system on which you run IMS/TM:
 - pgaflip.asm is assembler source for IMS FLIP transaction;



- pgaflip.jcl is JCL to assemble and linkedit IMS FLIP transaction;
- imsgen.asm is IMS stage 1 gen definitions for the IMS FLIP transaction.
- 5. Add the statements in the imsgen.asm file to your IMS stage 1 gen and run your IMS stage 1 and stage 2 gens. Use the online change utility to enable the new transaction definition.
- 6. Using the comments in the pgaflip.jcl file, tailor the JCL to match your system setup and submit it for batch execution. This assembles and linkedits the pgaflip.asm file into a load module library that is accessible to your IMS/TM system and creates a PSB and an ACB for the FLIP transaction.
- 7. Perform the tasks necessary on your system to make the new transaction available to IMS/TM. Depending on your system setup, you might have to restart IMS.
 - The IMS/TM configuration is now complete.

Configuring APPC/MVS

If your OLTP is APPC/MVS, then perform the following steps to configure APPC/MVS for communication with the gateway:

- 1. Configure MVS VTAM for the SNA APPC connection to Windows. At least one independent LU must be available for use by the gateway.
- 2. Check the VTAM logmode table used by APPC/MVS. (The table name is specified by the MODETAB parameter in the VTAM APPL definition for APPC/MVS.) Ensure that an entry exists for APPC sessions with SYNCLEVEL and parallel session support. The oraplu62.asm file in the %ORACLE_HOME%\dg4appc\sna directory contains a sample mode entry, including comments that indicate the required values in the mode entry.
- 3. Allocate a partitioned dataset (PDS) on your z/OS system where the sample files are placed. The PDS should be allocated with RECFM=FB, LRECL=80, and a BLKSIZE suitable for the device type on which it resides. Approximately two tracks of 3390 disk space are required with one directory block. Oracle suggests naming this partitioned dataset (PDS) ORAPGA, APPCMVS, SAMPLIB.
- 4. Using the file transfer facility, transfer the following files from the <code>%ORACLE_HOME%</code> \dg4appc\demo\MVS directory to the z/OS PDS you allocated in the previous step, using the following specified member names:
 - pgaflip.jcl is JCL to add an APPC/MVS TP profile and to define the execution environment for the transaction. Store this file in your z/OS PDS as member PGAFLIPJ.
 - pgaflip.rex is the REXX source for the APPC/MVS PGAFLIP transaction. Store this file in your z/OS PDS as member PGAFLIP.
- 5. Using the comments in the pgaflip.jcl file, tailor the JCL to match your system setup and submit it for batch execution. Performing this step defines the APPC/MVS TP profile for the PGAFLIP transaction and stores it in the APPC/MVS profile dataset. Ensure that you change the dataset name in the JCL to match the name of the z/OS PDS allocated in Step 3.

The APPC/MVS configuration is now complete.

 Now that you have completed configuration of the network on a gateway using the SNA protocol, proceed to Gateway Configuration Using SNA Communication Protocol.



• If you wish to configure commit-confirm, then instructions for this configuration can be found in Configuring Commit-Confirm.

7.2 Configuring the OLTP for Your TCP/IP Environment

These are the steps for configuring the OLTP to communicate with Oracle Database Gateway for APPC using TCP/IP for IMS Connect. IMS/TM, through IMS Connect, is the only supported OLTP for this release of the gateway.

Perform the following steps to configure IMS/TM and z/OS for communication with the gateway:

- 1. Configure the IMS system.
- 2. Configure IMS Connect.

For information on how to configure IMS Connect, refer to the IBM *IMS Connect Guide and Reference*.

- 3. Using your file transfer facility, transfer the following files from the <code>%ORACLE_HOME%</code> \dq4appc\demo\IMS directory to the z/OS system on which you run IMS/TM:
 - pgaflip.asm is assembler source for IMS FLIP transaction;
 - pgaflip.jcl is JCL to assemble and linkedit IMS FLIP transaction;
 - imsgen.asm is IMS stage 1 gen definitions for the IMS FLIP transaction.
- 4. Add the statements in the imsgen.asm file to the IMS stage 1 gen and run your IMS stage 1 and stage 2 gens. Use the online change utility to enable the new transaction definition.
- 5. Using the comments in the pgaflip.jcl file, tailor the JCL to match your system setup and submit it for batch execution. This assembles and linkedits the pgaflip.asm file into a load module library that is accessible to your IMS/TM system and creates a PSB and an ACB for the FLIP transaction.
- 6. Perform the tasks necessary on your system to make the new transaction available to IMS/TM. Depending on your system setup, you might have to restart IMS.

The IMS/TM configuration is now complete.

 At this point, proceed to Gateway Configuration Using TCP/IP Communication Protocol to complete configuration of the gateway and its components.



8

Configuring the Gateway Using SNA Communication Protocol

The following topics outline the steps needed to configure the Oracle database for a gateway using the SNA protocol on the Microsoft Windows platform. They show you how to configure commit-confirm, should you choose to implement it. The topics also provide the steps to verify installation and configuration of the gateway components, including optional commit-confirm.

- Before You Begin
- Preparing to Configure a Gateway Installation/Upgrade
- Integrating Server Configuration: First-Time Gateway Installations
- Upgrading or Migrating the Oracle Database from Previous Gateways
- Configuring the Oracle Database for Gateways to Coexist
- Optional Configuration Steps to Permit Multiple Users
- · Configuring the Gateway
- Configuring Commit-Confirm
- Verifying the Gateway Installation and OLTP Configuration
- Performing Postinstallation Procedures

Configuring the Oracle Database Gateway for APPC using SNA involves working with the following components:

- the Oracle database
- · your Microsoft Windows system
- your network
- the OLTP

8.1 Before You Begin

The following topics require you to input parameters unique to your system in order to properly configure the gateway and SNA communications interface.

Refer to Configuration Worksheet for a worksheet listing the installation parameters you will need to know before you can complete the configuration process. Ask your network administrator to provide you with these unique parameter names before you begin.

8.2 Preparing to Configure a Gateway Installation/Upgrade

There are three ways to establish the gateway-Oracle database relationship when you are installing or upgrading/migrating the gateway:

- When the Oracle Database and the gateway are installed in the same ORACLE HOME on the same machine
- When the Oracle Database and the gateway are installed on separate machine
- When the Oracle Database and the gateway are on the same machine but in different directories

Depending on the location of your gateway and your Oracle database, you may need to transfer some of the gateway administrative files to the location where your Oracle database is installed.

Follow the instructions suitable to your combination of the gateway-Oracle database locations listed below.

When the Oracle Database and the gateway are installed in the same ORACLE HOME on the same machine

You do not need to transfer files. Proceed to "Integrating Server Configuration: First-Time Gateway Installations".

When the Oracle Database and the gateway are installed on separate machine

- 1. Locate the gateway administrative files in the gateway <code>%ORACLE_HOME%</code> \dg4appc\admin directory. All files in this directory that have the suffix .sql, .pkh, and .pkb must be copied into a similarly-named directory in the Oracle database's Oracle home directory.
- 2. Now, locate the gateway demo files and subdirectories in the gateway's %ORACLE_HOME%\dg4appc\demo directory. Copy the pgavsn.sql and pgaecho.sql files into a similarly named directory in the Oracle database.
- 3. Copy the other subdirectories and files related to your installed OLTP on your remote host. For example, if you have CICS as your only OLTP, then copy the gateway <code>%ORACLE_HOME%\dg4appc\demo\CICS</code> files into a similarly named directory in the Oracle database.



Before transferring the files from the <code>%ORACLE_HOME%\dg4appc\demo</code> directory, make sure that you have generated your required TIPs. You need to transfer the TIPs as well.

Refer to the *Oracle Database Gateway for APPC User's Guide* for information about generating TIPs using PGAU.

When the Oracle Database and the gateway are on the same machine but in different directories

You must change your gateway's Oracle home to the Oracle database 's Oracle home directory.

1. For example, if your gateway's Oracle home is set as follows:

C:\> echo %ORACLE_HOME%
C:\oracle\pga\12.2



and your server's Oracle home is located in the $\protect\pro$

```
C:\> SET ORACLE HOME=C:\oracle\pga\12.2
```

2. Now create the directories with the following commands:

```
C:\> cd %ORACLE_HOME%
C:\> mkdir dg4appc
C:\> mkdir dg4appc\admin
```

- 3. Use whatever file transfer mechanism is available on your system to copy all the .sql, .pkh, and .pkb files from the gateway Oracle home %ORACLE_HOME% \dg4appc\admin directory to the Oracle database 's Oracle home %ORACLE_HOME% \dg4appc\admin directory.
- 4. You may also transfer the demo files from the gateway directory to the Oracle database directory. Copy the files and the directory recursively from the gateway Oracle home %ORACLE_HOME%\dg4appc\demo directory to the Oracle database %ORACLE_HOME% \dg4appc\demo directory.

For example:

```
C:\> cd %ORACLE_HOME%\dg4appc
C:\> mkdir\demo
C:\> cd demo
C:\> xcopy C:\oracle\pga\12.2\demo /E /I /Q
```

Note:

Before transferring the files from the <code>%ORACLE_HOME%\dg4appc\demo</code> directory, make sure that you have generated the required TIPs. You need to transfer the TIPs as well.

Refer to the *Oracle Database Gateway for APPC User's Guide* for information about generating TIPs using PGAU.

If this is a first-time installation, then proceed with "Integrating Server Configuration: First-Time Gateway Installations".

If this is an upgrade, then proceed with "Upgrading or Migrating the Oracle Database from Previous Gateways".

Following those steps, you may want to perform the Optional Configuration Steps to Permit Multiple Users, Optional Configuration Steps to Permit Multiple Users.

8.3 Integrating Server Configuration: First-Time Gateway Installations

Follow these steps to configure your Oracle database if you have installed Oracle Database Gateway for APPC for the first time:

- Ensure that the UTL_RAW PL/SQL package has been installed on your Oracle database.
 All PGAU-generated TIP specifications use UTL_RAW, which provides routines for manipulating raw data.
 - a. Use SQL*Plus to connect to the Oracle database as user SYS.



b. From SQL*Plus, enter the following command:

```
SOL> DESCRIBE UTL RAW
```

The DESCRIBE statement produces output on your screen. If you browse through the output, then you should see some functions, including a compare function. If you do not see this output, then continue the \mathtt{UTL}_{RAW} installation by performing Step 1.d. below.

If the <code>DESCRIBE</code> statement indicates success, then your Oracle database has <code>UTL RAW</code> installed and you can proceed to Step 2.

- c. Use SQL*Plus to connect to the Oracle database as user SYS.
- d. From SQL*Plus, run the utlraw.sql and prvtrawb.plb scripts in the Oracle database 's %ORACLE HOME%\rdbms\admin directory, in the following order:

```
C:\> cd %ORACLE_HOME%\rdbms\admin
SQL> @utlraw.sql
SQL> @prvtrawb.plb
```

- 2. Ensure that the DBMS_OUTPUT standard PL/SQL package is enabled on your Oracle database. The sample programs and installation verification programs on the distribution media use this standard package.
 - If necessary, then use SQL*Plus to connect to the Oracle database as user SYS.
 - **b.** From SQL*Plus, enter the following command:

```
SQL> DESCRIBE DBMS OUTPUT
```

The DESCRIBE statement produces output on your screen. If you browse through that output, you should see some functions, including a put_line function.

If you do not see this output, then you must create the <code>DBMS_OUTPUT</code> package. Refer to the *Oracle Database PL/SQL Packages and Types Reference* for more information about creating the <code>DBMS_OUTPUT</code> package. After successful installation of the <code>DBMS_OUTPUT</code> package, issue the <code>DESCRIBE</code> statement.

If the DESCRIBE statement indicates success, then your Oracle database has DBMS OUTPUT created, and you can proceed to Step 3.

- 3. Install the UTL_PG PL/SQL package. All PGAU-generated TIP specifications use UTL_PG, which provides routines for performing numeric conversions to and from raw data.
 - If necessary, then use SQL*Plus to connect to the Oracle database as user SYS.
 - b. From SQL*Plus, run the utlpg.sql and prvtpgb.plb scripts in the Oracle database 's %ORACLE HOME%\rdbms\admin directory, in the following order:

```
C:\> cd %ORACLE_HOME%\rdbms\admin
SQL> @utlpg.sql
SQL> @prvtpgb.plb
```

- 4. Install the Heterogeneous Services (HS) catalogs.
 - a. If necessary, use SQL*Plus to connect to the Oracle database as user SYS.
 - b. Enter the following command:

```
SQL> DESCRIBE HS_FDS_CLASS
```



The DESCRIBE statement produces output on your screen. If the DESCRIBE statement indicates success, then heterogeneous services catalogs have been created on your Oracle database and you can proceed to Step 5. otherwise follow the next step only if the DESCRIBE statement does not indicate success. The next step will create the Heterogeneous Services catalog.

c. If it is necessary to create the Heterogeneous Services catalog, then enter the following command:

```
C:\> cd %ORACLE_HOME%\rdbms\admin
SQL> @caths.sql
```

5. Create a public database link to access Oracle Database Gateway for APPC:

Use SQL*Plus to connect to the Oracle database as user SYSTEM. You can use the following SQL*Plus sample whether the Oracle database and the gateway are on the same system or on different systems. In the following sample, pgasrv is the tns_name_entry that will be assigned to the gateway when you modify the tnsnames.ora file later.

```
SQL> CREATE PUBLIC DATABASE LINK PGA USING 'PGASRV'
```

- 6. Create the gateway administrator user PGAADMIN and install the PG DD.
 - a. Use SQL*Plus to connect to the Oracle database as user SYSTEM.
 - b. From SQL*Plus, run the pgacr8au.sql script in the <code>%ORACLE_HOME%\dg4appc\admin</code> directory. This script creates the <code>PGAADMIN</code> user ID.

The initial password defined for PGAADMIN is PGAADMIN. Use the ALTER USER command to change the password. For further information about password issues, refer to the *Oracle Database SQL Language Reference*.

```
C:\> cd \GRACLE\_HOME \dg4appc\admin SQL> \ensuremath{\Gpgacr8au.sql}
```

- c. Use SQL*Plus to connect to the Oracle database as user PGAADMIN.
- d. From SQL*Plus, run the pgddcr8.sql script in the <code>%ORACLE_HOME%\dg4appc\admin</code> directory. This script installs the PG DD.

```
C:\> cd %ORACLE_HOME%\dg4appc\admin
SQL> @pgddcr8.sql
```

- e. From SQL*Plus, connect to the Oracle database as user SYS.
- f. Grant execution privileges on DBMS PIPE to PGAADMIN:

```
SQL> GRANT EXECUTE ON DBMS_PIPE TO PGAADMIN
```

- 7. Install the TIP trace access PL/SQL routines. These routines require that the DBMS_PIPE standard PL/SQL package is installed and that PGAADMIN has execute privileges on it. For more information on DBMS_PIPE, refer to the Oracle Database PL/SQL Packages and Types Reference.
 - **a.** If necessary, then use SQL*Plus to connect to the Oracle database as user PGAADMIN.
 - b. From SQL*Plus, run the pgatiptr.sql script in the %ORACLE_HOME%\dg4appc\admin directory. This script creates PL/SQL routines that can be called to read and purge trace information created by PGAU-generated TIP specifications. It also creates public synonyms for these routines. The script prompts you for the necessary user IDs and passwords.



```
C:\> cd %ORACLE_HOME%\dg4appc\admin
SQL> @pgatiptr.sql
```

- 8. Install the GPGLOCAL package. This package is required for compilation and execution of all PGAU-generated TIP specifications. TIP developers should be granted execute privileges on GPGLOCAL (refer to Step 3 of "Optional Configuration Steps to Permit Multiple Users").
 - a. Use SQL*Plus to connect to the Oracle database as user PGAADMIN.
 - b. From SQL*Plus, run the gpglocal.pkh script in the %ORACLE_HOME%
 \dg4appc\admin directory. This script compiles the GPGLOCAL package specification.

```
C:\> cd %ORACLE_HOME%\dg4appc\admin
SQL> @gpglocal.pkh
```

c. From SQL*Plus, run the gpglocal.pkb script in the %ORACLE_HOME% \dg4appc\admin directory. This script compiles the GPGLOCAL package body.

```
C:\> cd %ORACLE_HOME%\dg4appc\admin
SQL> @gpglocal.pkb
```

8.4 Upgrading or Migrating the Oracle Database from Previous Gateways

Follow these instructions *only* if you have a previous version of the Oracle Database Gateway for APPC installed on your system and need to configure it for 12c Release 2 (12.2) of the gateway.

- Upgrade your Oracle Database Gateway for APPC to current version levels as follows:
 - a. Use SQL*Plus to connect to the Oracle database as user SYS.
 - b. Install the UTL_RAW package body. From SQL*Plus, run the prvtrawb.plb script from the %ORACLE_HOME%\rdbms\admin directory. This script upgrades the UTL_RAW package body.

```
C:\> cd %ORACLE_HOME%\rdbms\admin
SQL> @prvtrawb.plb
```

c. Install the UTL_PG package body. From SQL*Plus, run the prvtpgb.plb script from the %ORACLE_HOME%\rdbms\admin directory. This script upgrades the UTL PG package body.

```
C:\> cd %ORACLE_HOME%\rdbms\admin
SQL> @prvtpqb.plb
```

The prvtrawb.plb and prvtpgb.plb scripts should complete successfully. If they fail because specifications do not exist or were invalidated, then consider reinstalling the package specifications as directed in If You Must Reinstall Package Specifications.



8.4.1 If You Must Reinstall Package Specifications

If the <code>UTL_RAW</code> or <code>UTL_PG</code> package has been invalidated or removed, then the <code>prvtrawb.plb</code> and <code>prvtpgb.plb</code> scripts may not complete successfully, then, you might have to reinstall the package specifications.

If you do reinstall the package specifications, then any dependent objects (such as existing user TIPs and client applications) are invalidated and will subsequently need to be recompiled. The impact of this is a one-time performance delay while recompilation of the TIPs and dependent client applications proceeds.



Before proceeding with reinstallation of the package scripts, make sure that you are in the ${ORACLE\ HOME}\dg4appc\admin\ directory.}$

TIPs were split into separate specification and body files in release 3.3 to avoid cascaded recompilations in later releases.

Step 1 Run the following scripts before proceeding with the PGAU upgrade

- 1. If necessary, then use SQL*Plus to connect to the Oracle database as user SYS.
- 2. From SQL*Plus, run the utlraw.sql and utlpg.sql scripts in the Oracle database %ORACLE_HOME%\rdbms\admin directory, in the following order, to upgrade their respective package specifications:

```
C:\> cd %ORACLE_HOME%\rdbms\admin
SQL> @utlraw.sql
SQL> @utlpg.sql
```

Step 2 Repeat installation of UTL_RAW and UTL_PG package body

After the scripts have run, repeat Steps 1b. and c. in Upgrading or Migrating the Oracle Database from Previous GatewaysUpgrading or Migrating the Oracle Database from Previous Gateways. Then, proceed to the section titled "Upgrading PGAU from Previous Gateway Releases".



TIPs and dependent client applications must be recompiled after reinstallation of the package specifications. Refer to the "Compiling a TIP" section in Chapter 3 of the *Oracle Database Gateway for APPC User's Guide* for information about compiling TIPs.

8.4.2 Upgrading PGAU from Previous Gateway Releases

- 1. Upgrade the PG DD as follows before executing the new PGAU:
 - If necessary, then use SQL*Plus to connect to the Oracle database as user PGAADMIN.



b. From SQL*Plus, run the pgddupgr.sql script in the %ORACLE_HOME% \dg4appc\admin directory. This script upgrades the PG DD.

```
C:\> cd %ORACLE_HOME%\dg4appc\admin
SQL> @pgddupgr.sql
```

8.5 Configuring the Oracle Database for Gateways to Coexist

You may have an older version of the gateway already installed. Be aware that although a version 10 gateway can communicate with a version 9 data dictionary (PG DD), a version 9 gateway cannot communicate with a version 10 data dictionary. So, if you upgrade your data dictionary to version 10, no gateways which were configured with a version 9 data dictionary will be able to communicate with it.

8.6 Optional Configuration Steps to Permit Multiple Users

The following configuration steps are optional. Perform these steps if you want to permit users other than PGAADMIN to perform PG DD operations using PGAU.

- 1. Create public synonyms for the PG DD to allow other users to access the tables:
 - a. Use SQL*Plus to connect to the Oracle database as user SYSTEM.
 - b. From SQL*Plus, run the pgddcr8s.sql script in the <code>%ORACLE_HOME%</code> \dg4appc\admin directory. This script creates public synonyms for the PG DD.

```
C:\> cd %ORACLE_HOME%\dg4appc\admin
SQL> @pgddcr8s.sql
```

- Create roles for accessing the PG DD, performing definitions of transactions, and generating TIP specifications. The PGAADMIN user can grant these roles to other users as necessary.
 - a. Use SQL*Plus to connect to the Oracle database as user PGAADMIN.
 - b. From SQL*Plus, run the pgddcr8r.sql script in the %ORACLE_HOME% \dg4appc\admin directory. This script creates two roles, PGDDDEF and PGDDGEN. The PGDDDEF role provides SELECT, INSERT, UPDATE, and DELETE privileges against some of the PG DD tables, and select privileges against others, and allows execution of the PGAU DEFINE, GENERATE, REDEFINE, REPORT, and UNDEFINE statements. The PGDDGEN role provides select privileges against the PG DD tables, and allows execution of the PGAU GENERATE and REPORT statements only.

```
C:\> cd %ORACLE_HOME%\dg4appc\admin
SQL> @pgddcr8r.sql
```

Grant access to PGA required packages.

TIP developers require access to the following PL/SQL packages, which are shipped with the Oracle database :

- DBMS PIPE in the %ORACLE HOME%\rdbms\admin directory
- UTL RAW in the %ORACLE HOME%\rdbms\admin directory
- UTL PG in the %ORACLE HOME%\rdbms\admin directory



Explicit grants to execute these packages must be made to TIP developers.

These grants can be private, as in the following example:

```
C:\> sqlplus SYS\PW@ database_specification_string
SQL> GRANT EXECUTE ON UTL_RAW TO tip_developer;
SQL> GRANT EXECUTE ON UTL_PG TO tip_developer;
SQL> GRANT EXECUTE ON DBMS_PIPE TO tip_developer;
SQL> CONNECT PGAADMIN\PW@ database_specification_string
SQL> GRANT EXECUTE ON PGAADMIN.PURGE_TRACE TO tip_developer;
SQL> GRANT EXECUTE ON PGAADMIN.READ_TRACE TO tip_developer;
SQL> GRANT EXECUTE ON PGAADMIN.GPGLOCAL TO tip_developer;
SQL> GRANT EXECUTE ON PGAADMIN.GPGLOCAL TO tip_developer;
```

Alternatively, these grants can be public, as in the following example:

```
C:\> sqlplus SYS\PW@database_specification_string
SQL> GRANT EXECUTE ON UTL_RAW TO PUBLIC;
SQL> GRANT EXECUTE ON UTL_PG TO PUBLIC;
SQL> GRANT EXECUTE ON DBMS_PIPE TO PUBLIC;
SQL> CONNECT PGAADMIN\PW@ database_specification_string
SQL> GRANT EXECUTE ON PGAADMIN.PURGE_TRACE TO PUBLIC;
SQL> GRANT EXECUTE ON PGAADMIN.READ_TRACE TO PUBLIC;
SQL> GRANT EXECUTE ON PGAADMIN.GPGLOCAL TO PUBLIC;
SQL> EXIT
```

You can use either private or public grants. Both grants are sufficient for using PGA. Public grants are easier and can be performed now. If you use private grants, then they must be issued each time a new TIP developer user ID is created.

SQL scripts for performing these grants are provided in the <code>%ORACLE_HOME%</code> \dg4appc\admin directory. Thepgddapub.sql script performs these grants for public access to the packages. The pgddadev.sql script performs the grants for private access to the packages by a single TIP developer. If you are going to use private grants, then you must run the pgddadev.sql script once for each TIP developer's user ID:

- a. Use SQL*Plus to connect to the Oracle database as user PGAADMIN.
- b. From SQL*Plus, run the suitable script (pgddapub.sql or pgddadev.sql) from the %ORACLE_HOME%\dg4appc\admin directory. The script performs the necessary grants as described earlier. You are prompted for the required user IDs, passwords, and database specification strings.

If you are using private grants, then repeat this step for each user ID requiring access to the packages.

```
C:\> cd %ORACLE_HOME%\dg4appc\admin
SQL> @pgddapub.sql

Or
SQL> @pgddadev.sql
```

4. If you are upgrading from a previous release of the gateway and if you want to upgrade your existing TIPs with new function and maintenance, then regenerate existing TIP specifications using the PGAU GENERATE statement.





The Procedural Gateway Administrative Utility (PGAU) has been enhanced to automatically upgrade existing PG DD entries with a new attribute when a PGAU GENERATE command is executed. To support this enhancement, add a new privilege to the PGDDGEN role. To do this, as the PGAADMIN user, use SQL*Plus to connect to the Oracle database where the PG DD is stored. Then issue the following SQL command:

```
SQL> GRANT INSERT ON PGA_DATA_VALUES TO PGDDGEN
```

a. Start PGAU from the directory path where the PGAU control files are generated and where TIPs are stored:

```
C:\> pgau
PGAU> CONNECT PGAADMIN\pgaadmin@database_specification_string
PGAU> GENERATE tranname
PGAU> EXIT
```

For more information about the GENERATE command, refer to the PGAU GENERATE command section in Chapter 2 of the *Oracle Database Gateway for APPC User's Guide*.

Note that it is not necessary to define the PG DD entries again.

5. Start SQL*Plus in the same directory path where the newly-generated TIP specifications are stored.

```
C:\> sqlplus tip_owner\pw@database_specification_string
SQL> @tipname.pkh
SQL> @tipname.pkb
SQL> exit
```

PGAU GENERATE produces the TIP in two output file, a specification and a body. You must compile both, first the specification and then the body.

For more information about the GENERATE command, refer to the PGAU GENERATE command section in Chapter 2 of the *Oracle Database Gateway for APPC User's Guide*.

8.7 Configuring the Gateway

To configure the gateway, perform the following steps:

Customize the Oracle Database Gateway for APPC parameters.

Parameters specific to the gateway are supplied in the gateway parameter file, initsid.ora, which is in the <code>%ORACLE_HOME%\dg4appc\admin</code> directory. A sample gateway parameter file, initPGA.ora, is provided in this subdirectory.



Note:

In the initsid.ora file, substitute your dg4appc SID name for "sid" in this file name.

The <code>initsid.ora</code> file contains both APPC and TCP/IP parameters, separated by a description. You must modify the <code>initsid.ora</code> file by deleting the TCP/IP parameters. Refer to Gateway Initialization Parameters for SNA Protocol for the valid APPC parameters.

The parameters fall into two categories:

gateway initialization parameters

These parameters control the general operation of the gateway in the Oracle environment.

Note:

Before performing the following step, refer to Gateway Initialization

Parameters for SNA Protocol for information about tailoring gateway
initialization and PGA parameters. Pay special attention to the information
about using the PGA_CAPABILITY parameter.

PGA parameters

PGA parameters control the APPC interface portion of the gateway. Use the SET gateway initialization parameter to specify PGA parameters. Oracle recommends that you group all SET commands for PGA parameters at the end of the initsid.ora file.

Note:

Misspelled parameters are ignored. However, if the <code>%ORACLE_HOME%</code> \dg4appc\admin\initsid.ora file is missing, then all calls to the gateway fail and return a PGA-20928 error.

If you do not plan to configure commit-confirm, then proceed to "Verifying the Gateway Installation and OLTP Configuration".



8.8 Configuring Commit-Confirm

Note:

If you are planning to implement commit-confirm, then read the detailed explanation of commit-confirm capabilities in Chapter 5 of the *Oracle Database Gateway for APPC User's Guide*, "Implementing Commit-Confirm (SNA Only) before proceeding.

Follow these steps to configure the commit-confirm components.

The steps for configuring commit-confirm include:

- configuring the Oracle database where the gateway server will store its transaction log information
- configuring the gateway initialization parameters, and
- configuring the OLTP.

All these steps must be performed before attempting to use any application that uses commit-confirm.

8.8.1 Configuring the Oracle Database for Commit-Confirm

The Oracle database where the gateway server will store its transaction log information should ideally be on the same system where the gateway runs. The configuration of the server consists of creating the gateway DBA user, creating the commit-confirm log tables and creating the PL/SQL stored procedure used by the gateway server for logging transactions.

The pgaccau.sql script from the $ORACLE_HOME \dg4appc\admin$ directory creates the gateway DBA user ID. The default user ID is PGADBA with the initial password set to PGADBA. If you want to change the user ID or initial password, you must modify the script.

- 1. Use SQL*Plus to connect to the Oracle database as user SYSTEM.
- 2. From SQL*Plus, run the pgaccau.sql script from the <code>%ORACLE_HOME%</code>
 \dg4appc\admin directory. This script creates the gateway DBA user ID. If you want to change the password at any time after running this script, then you can use the ALTER USER command to change the password. For further information, refer to the Oracle Database SQL Language Reference.
- 3. Use SQL*Plus to connect to the Oracle database as user PGADBA.
- 4. From SQL*Plus, run the pgaccpnd.sql script from the %ORACLE_HOME% \dg4appc\admin directory. This script creates the PGA_CC_PENDING table used by the gateway server for its commit-confirm transaction log.
- 5. From SQL*Plus, run the pgacclog.sql script from the %ORACLE_HOME% \dg4appc\admin directory. This script creates the PGA_CC_LOG PL/SQL stored procedure used by the gateway server for updating the PGA_CC_PENDING table.



6. Disconnect from the Oracle database.

8.8.2 Configuring Gateway Initialization Parameters for Commit-Confirm

The gateway initialization parameters are described in Gateway Initialization Parameters for SNA Protocol. The parameters necessary for commit-confirm support in the gateway are:

- PGA CAPABILITY
- PGA LOG DB
- PGA LOG USER
- PGA LOG PASS
- PGA_RECOVERY_USER
- PGA RECOVERY PASS
- PGA RECOVERY TPNAME

These parameters should be added to your initsid.ora file, where sid is the gateway SID for the commit-confirm gateway.

Refer to Gateway Initialization Parameters for SNA Protocol for full information about the gateway initialization parameters supported by the Oracle Database Gateway for APPC.

8.8.3 Configuring the OLTP for Commit-Confirm

Configuration of the OLTP includes the following:

- defining and installing the commit-confirm transaction log database
- defining and installing the commit-confirm forget/recovery transaction
- defining and installing the sample commit-confirm applications provided with the gateway.



A restart of the OLTP may be necessary to implement the changes required for commit-confirm support. You should plan for this with your OLTP system administrator.

Detailed instructions for configuring the Transaction Server for z/OS and IMS/TM are provided in the <code>%ORACLE_HOME%\dg4appc\demo\CICS\README.doc</code> and <code>%ORACLE_HOME% \dg4appc\demo\IMS\README.doc</code> files, respectively.

Refer to Chapter 5, "Implementing Commit-Confirm (SNA Only)" in the *Oracle Database Gateway for APPC User's Guide* for detailed information about commit-confirm.

You will take steps to verify configuration of commit-confirm later, in Verifying OLTP Configuration for Commit-ConfirmVerifying OLTP Configuration for Commit-Confirm.

However, first proceed to Verifying the Gateway Installation and OLTP Configuration to verify the gateway installation.



8.9 Verifying the Gateway Installation and OLTP Configuration

To verify the gateway installation and the OLTP configuration, perform the following procedures after installing Oracle Database Gateway for APPC. In addition, if you chose to configure commit-confirm, then follow the steps to verify the OLTP configuration for commit-confirm.



If your database link name is not PGA, then modify the demonstration .sql files to give them the particular database link name that you created in Step 5 of "Integrating Server Configuration: First-Time Gateway Installations". You must modify the following .sql files:

- pgavsn.sql
- pgaecho.sql
- pgacics.sql
- pgaidms.sql
- pgaims.sql
- pgamvs.sql

8.9.1 Verifying the Gateway Installation

To verify the gateway software installation using the database link PGA previously created, perform the following steps:

- Using SQL*Plus, connect to the Oracle database as user PGAADMIN.
- 2. Run %ORACLE HOME%\dg4appc\demo\pgavsn.sql.

```
C:\> cd %ORACLE_HOME%\dg4appc\demo
SQL> @pgavsn.sql
```

The server version number banner appears at your terminal. You will receive the following output:

```
Oracle Database Gateway for APPC.
Version 11.2.0.0.2 Thu Jun 11 14:39:15
2009

Copyright (c) Oracle Corporation 1979, 2009. All rights reserved.

PL/SQL procedure successfully completed.
```

3. Run %ORACLE_HOME%\dg4appc\demo\pgaecho.sql.

```
C:\> cd %ORACLE_HOME%\dg4appc\demo
SQL> @pgaecho.sql
```



You will receive the following output:

==> Congratulations, your installation was successful. <==

8.9.2 Verifying the OLTP Configuration

The procedure for verifying the OLTP configuration varies, depending on which OLTP you are using and depending on the platform the OLTP is running on. CICS Transaction Server for z/OS, IMS/TM, APPC/MVS and z/OS are the currently supported OLTPs. Follow the instructions for verifying the installation.



If you have not completed the file transfers detailed in "Preparing to Configure a Gateway Installation/Upgrade", then complete them now, before proceeding to the next step.

8.9.2.1 CICS Verification

If your OLTP is CICS Transaction Server for z/OS, then perform the following steps to verify the CICS configuration.

1. To verify that the FLIP transaction is installed correctly, log on to your CICS Transaction Server for z/OS and enter the following transaction, replacing FLIP with the transaction ID you chose for FLIP when you configured your CICS Transaction Server for z/OS for the gateway:

FLIP THIS MESSAGE

The following output appears at your terminal:

EGASSEM SIHT PILF

2. From the Windows platform, modify the pgacics.sql file which resides at <code>%ORACLE_HOME%</code> \dq4appc\demo\CICS\pgacics.sql.

Customize the following three items used for accessing the gateway and the CICS Transaction Server for z/OS, as described in the comments at the beginning of the file:

- the CICS transaction ID
- the side profile name
- the logmode entry name
- 3. Ensure that the SNA Server on the system has been started.
- 4. Log on to the CICS Transaction Server for z/OS and enter this transaction, where <code>name</code> is the name of the <code>CONNECTION</code> definition installed by the <code>DFHCSDUP</code> job you ran in the CICS configuration steps:

CEMT SET CONNECTION (name) ACQUIRED

This transaction activates the CICS connection to Windows.

- 5. Use SQL*Plus to connect to the Oracle database as PGAADMIN.
- 6. Run pgacics.sql.



```
C:\> cd %ORACLE_HOME%\dg4appc\demo\CICS
SQL> @pgacics.sql
```

The following message appears:

```
==> Congratulations, your gateway is communicating with CICS <==
```

The CICS Transaction Server for z/OS installation verification is complete.

8.9.2.2 IMS/TM Verification

If the OLTP is IMS/TM, then perform the following steps to verify the IMS/TM configuration:

1. To verify that the FLIP transaction is installed correctly, log on to the IMS/TM system and enter the following transaction, replacing FLIP with the transaction ID you chose for FLIP when you configured the IMS/TM system for the gateway:

```
FLIP THIS MESSAGE
```

The following output appears on the terminal:

```
EGASSEM SIHT PILF
```

2. From a Windows platform, modify the pgaims.sql file, which resides at

<code>%ORACLE_HOME%\dg4appc\demo\IMS\pgaims.sql.</code> Customize the following three items used for accessing the gateway and the IMS/TM system, as described in the comments at the beginning of the file:

- the IMS/TM transaction ID
- the side profile name
- the logmode entry name
- 3. Ensure that the SNA Server on the system has been started.
- 4. Use SQL*Plus to connect to the Oracle database as PGAADMIN.
- 5. Run pgaims.sql.

```
C:\> cd %ORACLE_HOME%\dg4appc\demo\IMS
SQL> @pgaims.sql
```

The following message appears:

```
==> Congratulations, your gateway is communicating with IMS/TM <==
```

The IMS/TM installation verification is now complete.

8.9.2.3 APPC/MVS Verification

If the OLTP is APPC/MVS, then perform the following steps to verify the APPC/MVS configuration:

- 1. Verify that the APPC/MVS subsystem is active.
- 2. From the Windows platform, modify the pgamvs.sql file, which resides at %ORACLE_HOME%\dg4appc\demo\MVS\pgamvs.sql. Customize the following three items used for accessing the gateway and the APPC/MVS system, as described in the comments at the beginning of the file:
 - the APPC/MVS transaction ID



- the side profile name
- the logmode entry name
- Ensure that the SNA Server on the system has been started.
- 4. Use SQL*Plus to connect to the Oracle database as PGAADMIN.
- 5. Run pgamvs.sql.

```
C:\> cd %ORACLE_HOME%\dg4appc\demo\MVS
SQL> @pgamvs.sql
```

The following message appears:

=> Congratulations, your gateway is communicating with APPC/MVS <=

The APPC/MVS installation verification is now complete.

8.9.3 Verifying OLTP Configuration for Commit-Confirm

If you chose to configure commit-confirm in Configuring Commit-Confirm, then the following section will assist you in verifying the configuration.



Refer to Chapter 5, "Implementing Commit-Confirm" in the *Oracle Database Gateway for APPC User's Guide* for background information about the components and capabilities of commit-confirm.

Samples are provided with the gateway for Transaction Server for z/OS and IMS/TM for implementing commit-confirm support. They are in the following directories, respectively: <code>%ORACLE_HOME%\dg4appc\demo\CICS</code> and <code>%ORACLE_HOME%\dg4appc\demo\IMS.</code> A README.doc file in each directory provides detailed information about installing and using the samples. JCL files for compiling and linking the sample programs are provided as well. The samples included with the gateway assist you with the following:

- Creating and initializing the commit-confirm transaction log databases and defining those databases to the OLTP. For Transaction Server for z/OS, the sample uses a VSAM file for the log database. For IMS/TM, a SHISAM/VSAM database is used.
- Using subroutines for receiving the Oracle Global Transaction ID from the gateway and logging it into the commit-confirm transaction log database. These subroutines are provided in the pgacclg.asm files. They can be used in the applications to reduce the complexity of the code changes to the programs.
 - For Transaction Server for z/OS, the subroutine provided is called using the EXEC CICS LINK interface. For IMS/TM, the subroutine provided is called using the standard CALL statement or its equivalent in the application's programming language. Both these subroutines are written in 370 assembler to eliminate any interlanguage interface complexities and compiler dependencies.
- Installing forget/recovery transactions in the OLTP. These are provided in the pgareco.asm files. Forget/recovery transactions must be accessible through APPC so that the gateway can call them to forget a transaction once it has been successfully committed, and to guery a transaction's state during recovery processing. These



transactions delete the entry for a particular Oracle Global Transaction ID from the OLTP commit-confirm transaction log database during forget processing, and query the entry for a particular Oracle Global Transaction ID from the OLTP commit-confirm transaction log database during recovery processing. For both Transaction Server for z/OS and IMS/TM, these transactions are written in 370 assembler.

Using the sample commit-confirm transaction log databases and subroutines. For Transaction Server for z/OS, a sample DB2 update transaction, DB2C, is provided in the pgadb2c.cob file. This is a COBOL example that updates the DB2 sample EMP table. For IMS/TM, a sample DLI update transaction, PGAIMSU, is provided in the pgaimsu.cob file. This is a COBOL example that updates the DLI sample PARTS database.

8.10 Performing Postinstallation Procedures

The following are optional steps that you can perform as necessary. Installation of the sample applications for your OLTP is recommended to help you to fully understand how the gateway works and how it interfaces with the OLTP.

8.10.1 Installing Sample Applications

The Oracle Database Gateway for APPC package contains sample PL/SQL procedures and OLTP transaction programs that demonstrate the capabilities of the gateway. Samples are provided for the following:

APPC/MVS

z/OS dataset information

CICS Transaction Server for z/OS

- DB2 inquiry
- DB2 multirow inquiry
- DB2 update
- VSAM inquiry
- VSAM update
- DLI inquiry
- FEPI DB2 inquiry
- FEPI VSAM inquiry

IMS/TM

- IMS inquiry using IVTNO and IVTNV sample transactions
- IMS PARTS inquiry (CPI-C)
- IMS PARTS update (CPI-C)

Additional samples are added to the distribution media in later releases of the product. Wherever possible, the sample applications use the sample databases provided with the database products.

For this release, full documentation on installing and using the sample applications is available in the README.doc files in the following directories:



- %ORACLE_HOME%\dg4appc\CICS\sample_CICS_applications.txt
- %ORACLE_HOME%\dg4appc\IMS\sample_IMS_applications.txt
- %ORACLE_HOME%\dg4appc\MVS\sample_MVS_applications.txt



9

Configuring the Gateway Using TCP/IP Communication Protocol

The following topics outline the steps to configure the Oracle database for a gateway using TCP/IP for IMS Connect on your Microsoft Windows platform. They also provide the steps to verify installation and configuration of the gateway and OLTP components.

- · Before You Begin
- Preparing to Configure a Gateway Installation/Upgrade
- Configuring the Oracle Database : First Time Installation
- Upgrading or Migrating the Oracle Database from Previous Gateways
- Optional Configuration Steps to Permit Multiple Users
- Configuring TCP/IP for the Gateway
- Configuring the Gateway
- Loading the PGA_TCP_IMSC Table
- Verifying the Gateway Installation and OLTP Configuration
- Performing Postinstallation Procedures

Configuring the Oracle Database Gateway for APPC using TCP/IP support for IMS Connect involves working with the following components:

- the Oracle database
- your Windows system
- · your network
- the OLTP

9.1 Before You Begin

The following topics require you to input parameters unique to your system in order to properly configure the gateway and TCP/IP communications interface.

Refer to Configuration Worksheet for a worksheet listing the installation parameters you will need to know before you can complete the configuration process. Ask your network administrator to provide you with these unique parameter names before you begin.

9.2 Preparing to Configure a Gateway Installation/Upgrade

There are three ways to establish the gateway-Oracle database relationship when you are installing or upgrading/migrating the gateway:

 When the Oracle Database and the gateway are installed in the same ORACLE_HOME on the same machine;

- When the Oracle Database and the gateway are installed on separate machine; or
- When the Oracle Database and the gateway are on the same machine but in different directories

Depending on the location of your gateway and your Oracle database, you may need to transfer some of the gateway administrative files to the location where the Oracle database is installed.

Follow the instructions suitable to your combination of the gateway-Oracle database locations listed below.

When the Oracle Database and the gateway are installed in the same ORACLE HOME on the same machine

You do not need to transfer files. Proceed to "Configuring the Oracle Database : First Time Installation".

When the Oracle Database and the gateway are installed on separate machine

- 1. Locate the gateway administrative files in the gateway <code>%ORACLE_HOME%</code> \dg4appc\admin directory. All files in this directory that have the suffix <code>.sql</code>, <code>.pkh</code>, and <code>.pkb</code> must be copied into a similarly-named directory in the Oracle database 's Oracle home directory.
- 2. Now locate the gateway demo files and subdirectories in the gateway %ORACLE_HOME%\dg4appc\demo directory. Copy the pgavsn.sql and pgaecho.sql files into a similarly named directory in the Oracle database.
- 3. Copy the pgaims.sql file from the gateway Oracle home %ORACLE_HOME% \dg4appc\demo\IMS directory to your Oracle database 's Oracle home %ORACLE HOME%\dg4appc\demo\IMS directory.
- 4. Optional Steps: If you want to run IVTNV and IVTNO, then you will need to copy the ivtno.ctl, ivtnod.sql, ivtnv.ctl, and ivtnvd.sql files into the Oracle database 's Oracle home %ORACLE_HOME%\dg4appc\demo\IMS directory as well. Make sure to generate the required TIPs and transfer them as well.

When the Oracle Database and the gateway are on the same machine but in different directories

You must change your gateway's Oracle home to the Oracle database 's Oracle home directory.

1. For example, if your gateway's Oracle home is set as follows:

```
C:\> echo %ORACLE_HOME%
C:\oracle\pga\12.2
```

and your server's Oracle home is located in the ' \protectory , then you need to do the following:

```
C:\> SET ORACLE_HOME=C:\oracle\pga\12.2
```

2. Now, create the directories with the following commands:

```
C:\> cd %ORACLE_HOME%
C:\> mkdir dg4appc
C:\> mkdir dg4appc\admin
C:\> mkdir dg4appc\demo
C:\> mkdir dg4appc\demo\IMS
```



- 3. Use whatever file transfer mechanism is available on your system to copy all the .sql, .pkh, and .pkb files from the gateway's Oracle home %ORACLE_HOME% \dg4appc\admin directory to the Oracle database 's Oracle home %ORACLE_HOME% \dg4appc\admin directory.
- 4. You may also transfer the demo files from the gateway directory to the Oracle database directory. Copy the pgavsn.sql and pgaecho.sql files and directory recursively from the gateway Oracle home's %ORACLE_HOME%\dg4appc\demo directory to the Oracle database 's %ORACLE HOME%\dg4appc\demo directory.
- 5. You may also copy the pgaims.sql file from the gateway Oracle home <code>%ORACLE_HOME% \dg4appc\demo\IMS directory</code> to the Oracle database Oracle home <code>%ORACLE_HOME% \dg4appc\demo\IMS directory</code>.

Optional Steps: If you want to run IVTNV and IVTNO, then you will need to copy the ivtno.ctl, ivtnod.sql, ivtnv.ctl, and ivtnvd.sql files into the Oracle database 's Oracle home <code>%ORACLE_HOME%\dg4appc\demo\IMS</code> directory as well. Make sure to generate the required TIPs and transfer them as well.

Proceed to "Configuring the Oracle Database: First Time Installation". Following those steps, you may want to perform the Optional Configuration Steps to Permit Multiple Users, Optional Configuration Steps to Permit Multiple Users.

9.3 Configuring the Oracle Database: First Time Installation

Follow these steps to configure the Oracle database after installing the Oracle Database Gateway for APPC.

- Ensure that the UTL_RAW PL/SQL package has been installed on the Oracle database. All PGAU-generated TIP specifications use UTL_RAW, which provides routines for manipulating raw data.
 - a. Use SQL*Plus to connect to the Oracle database as user SYS.
 - b. From SQL*Plus, enter the following command:

```
SQL> DESCRIBE UTL RAW
```

The DESCRIBE statement produces output on the screen. If you browse through the output, then you should see some functions, including a compare function. If you do not see this output, then continue the UTL RAW installation by performing Step 1.d.

If the DESCRIBE statement indicates success, then your Oracle database has UTL_RAW installed and you can proceed to Step 2.

- c. Use SQL*Plus to connect to the Oracle database as SYS.
- **d.** From SQL*Plus, run the utlraw.sql and prvtrawb.plb scripts in the Oracle database %ORACLE HOME%\rdbms\admin directory, in the following order:

```
C:\> cd %ORACLE_HOME%\rdbms\admin
SQL> @utlraw.sql
SQL> @prvtrawb.sql
```

- 2. Ensure that the DBMS_OUTPUT standard PL/SQL package is enabled on your Oracle database. The sample programs and installation verification programs on the distribution media use this standard package.
 - a. If necessary, then use SQL*Plus to connect to the Oracle database as user SYS.



b. Enter the following command:

```
SQL> DESCRIBE DBMS OUTPUT
```

The DESCRIBE statement produces output on your screen. If you browse through that output, then you should see some functions, including a put_line function.

If you do not see this output, then you must create the DBMS_OUTPUT package. Refer to the *Oracle Database PL/SQL Packages and Types Reference* for more information about the DBMS_OUTPUT package. After successful installation of the DBMS_OUTPUT package, issue the DESCRIBE statement.

If the DESCRIBE statement indicates success, then your Oracle database has DBMS OUTPUT created, and you can proceed to Step 3.

- Install the UTL_PG PL/SQL package. All PGAU-generated TIP specifications use UTL_PG, which provides routines for performing numeric conversions to and from raw data.
 - If necessary, then use SQL*Plus to connect to the Oracle database as user SYS.
 - b. From SQL*Plus, run the utlpg.sql and prvtpgb.plb scripts in the Oracle database 's %ORACLE HOME%\rdbms\admin directory, in the following order:

```
C:\> cd %ORACLE_HOME%\rdbms\admin
SQL> @utlpg.sql
SQL> @prvtpgb.plb
```

- 4. Install the Heterogeneous Services (HS) catalogs.
 - If necessary, then use SQL*Plus to connect to the Oracle database as user SYS.
 - **b.** Enter the following command:

```
SQL> DESCRIBE HS FDS CLASS
```

The DESCRIBE statement produces output on the screen. If the DESCRIBE statement indicates success, then Heterogeneous Services catalogs have been created on your Oracle database and you can proceed to Step 5.

If the DESCRIBE statement does not indicate success, then you must create Heterogeneous Services catalogs and you must perform Step 4.c below:

c. If it is necessary to create the Heterogeneous Services catalog, then enter the following command:

```
C:\> cd %ORACLE_HOME%\rdbms\admin
SQL> @caths.sql
```

5. Create a public database link to access the Oracle Database Gateway for APPC:

Use SQL*Plus to connect to the Oracle database as user SYSTEM. You can use the following SQL*Plus sample whether the Oracle database and the gateway are on the same system or on different systems. In the following sample, pgasrv is the tns_name_entry that will be assigned to the gateway when you modify the tnsnames.ora file later.

```
SOL> CREATE PUBLIC DATABASE LINK PGA USING 'PGASRV'
```

6. Create the gateway administrator user PGAADMIN and install the PG DD.



- a. Use SQL*Plus to connect to the Oracle database as user SYSTEM.
- b. From SQL*Plus, run the pgacr8au.sql script in the %ORACLE_HOME%\dg4appc\admin directory. This script creates the PGAADMIN user ID.

The initial password defined for PGAADMIN is PGAADMIN. Use the ALTER USER command to change the password. For further information about password issues, refer to the *Oracle Database SQL Language Reference*.

```
C:\> cd %ORACLE_HOME%\dg4appc\admin
SQL> @pgacr8au.sql
```

- c. Use SQL*Plus to connect to the Oracle database as user PGAADMIN.
- d. From SQL*Plus, run the pgddcr8.sql script in the %ORACLE_HOME%\dg4appc\admin directory. This script installs the PG DD.

```
C:\> cd %ORACLE_HOME%\dg4appc\admin
SQL> @pgddcr8.sql
```

- e. From SQL*Plus, connect to the Oracle database as user SYS.
- f. Grant execution privileges on DBMS PIPE to PGAADMIN:

```
SQL> GRANT EXECUTE ON DBMS PIPE TO PGAADMIN
```

7. Ensure that the pg4tcpmap package has been installed on your Oracle database. Follow Steps a through c to test for proper installation of pg4tcpmap.

Refer to "Output for the pg4tcpmap Tool" in Gateway Initialization Parameters for TCP/IP Communication Protocol for a sample of the output from the pg4tcpmap tool, and refer to Chapter 6 of the *Oracle Database Gateway for APPC User's Guide* for details about the commands needed to run the tool.

- a. Use SQL*Plus to connect to the Oracle database as user SYSTEM.
- **b.** Enter the following command:

```
SQL> select table_name, owner
from dba_tables
where table_name = 'PGA_TCP_IMSC',
and owner = 'PGAADMIN';
SQL> column owner format a 10
SQL> column index_name format a 18
SQL> column table_name format a 14
SQL> select owner, index_name, table_name, uniqueness
from dba_indexes
where index_name = 'PGA_TCP_IMSC_IND';
```

Both SELECT statements must produce one row each. Following is the result for the first select statement:

TABLE_NAME	OWNER
PGA_TCP_IMSC	PGAADMIN

Following is the result of the second select statement:

OWNER	INDEX_NAME	TABLE_NAME	UNIQUENESS
PGAADMIN	PGA TCP IMSC IND	PGA TCP IMSC	UNIQUE



If the select statements produce the preceding output on the screen, then you can skip Step C. If the select statement produces no output or more than one row, then the result is not the same as the output described above, and it is necessary for you to perform Step 7.c.

c. From SQL*Plus, run the pgaimsc.sql script in the Oracle database 's %ORACLE HOME%\dq4appc\admin directory:

```
C:\> cd %ORACLE_HOME%\dg4appc\admin
SQL> @pgaimsc.sql
```

- 8. Install the TIP trace access PL/SQL routines. These routines require that the DBMS_PIPE standard PL/SQL package is installed and that PGAADMIN has execute privileges on it. For more information about DBMS_PIPE, refer to the *Oracle Database PL/SQL Packages and Types Reference*.
 - **a.** If necessary, then use SQL*Plus to connect to the Oracle database as user PGAADMIN.
 - b. From SQL*Plus, run the pgatiptr.sql script in the <code>%ORACLE_HOME%</code> \dg4appc\admin directory. This script creates PL/SQL routines that can be called to read and purge trace information created by PGAU-generated TIP specifications. It also creates public synonyms for these routines. The script prompts you for the necessary user IDs and passwords.

```
C:\> cd %ORACLE_HOME%\dg4appc\admin
SQL> @pgatiptr.sql
```

- Install the GPGLOCAL package. This package is required for compilation and execution of all PGAU-generated TIP specifications. TIP developers should be granted execute privileges on GPGLOCAL (refer to "Optional Configuration Steps to Permit Multiple Users").
 - a. Use SQL*Plus to connect to the Oracle database as user PGAADMIN.
 - b. From SQL*Plus, run the <code>gpglocal.pkh</code> script in the <code>%ORACLE_HOME%</code> \dg4appc\admin directory. This script compiles the <code>GPGLOCAL</code> package specification.

```
C:\> cd %ORACLE_HOME%\dg4appc\admin
SQL> @gpglocal.pkh
```

c. From SQL*Plus, run the gpglocal.pkb script in the <code>%ORACLE_HOME%</code> \dg4appc\admin directory. This script compiles the GPGLOCAL package body.

```
C:\> cd %ORACLE_HOME%\dg4appc\admin
SQL> @gpqlocal.pkb
```





Recompile TIPs when changing communication protocol from SNA to TCP/IP:

If you have existing TIPs that were generated previously on a gateway using the SNA protocol and you want to use the new TCP/IP feature, then the TIPs will have to be regenerated by PGAU with mandatory NLS_LANGUAGE and Side Profile Settings. Specify the suitable ASCII character set in the DEFINE TRANSACTION command.

This is due to the fact that the gateway assumes that the appropriate user exit in IMS Connect is being used, which would translate between the suitable ASCII and EBCDIC character sets.

9.4 Upgrading or Migrating the Oracle Database from Previous Gateways

Follow these instructions only if you have a previous version of the Oracle Database Gateway for APPC installed on your system and need to configure it for 12c Release 21 (12.2) of the gateway.

- 1. Upgrade your Oracle Database Gateway for APPC to current version levels as follows:
 - a. Use SQL*Plus to connect to the Oracle database as user SYS.
 - b. Install the UTL_RAW package body. From SQL*Plus, run the prvtrawb.plb script from the %ORACLE_HOME%\rdbms\admin directory. This script upgrades the UTL_RAW package body.

```
C:\> cd %ORACLE_HOME%\rdbms\admin
SQL> @prvtrawb.plb
```

c. Install the UTL_PG package body. From SQL*Plus, run the prvtpgb.plb script from the %ORACLE_HOME%\rdbms\admin directory. This script upgrades the UTL_PG package body.

```
C:\> cd %ORACLE_HOME%\rdbms\admin
SQL> @prvtpqb.plb
```

The prvtrawb.plb and prvtpgb.plb scripts should complete successfully. If they fail because specifications do not exist or were invalidated, then consider reinstalling the package specifications as directed in If You Must Reinstall Package Specifications.

9.4.1 If You Must Reinstall Package Specifications

If the <code>UTL_RAW</code> or <code>UTL_PG</code> package has been invalidated or removed, then the <code>prvtrawb.plb</code> and <code>prvtpgb.plb</code> scripts may not complete successfully, then, you might have to reinstall the package specifications.

If you do reinstall the package specifications, then any dependent objects (such as existing user TIPs and client applications) are invalidated and will subsequently need to be recompiled. The impact of this is a one-time performance delay while recompilation of the TIPs and dependent client applications proceeds.





TIPs were split into separate specification and body files in release 3.3 to avoid cascaded recompilations in later releases.

- Step 1: Run the following scripts before proceeding with the PGAU upgrade:
 - If necessary, then use SQL*Plus to connect to the Oracle database as user SYS.
 - 2. From SQL*Plus, run the utlraw.sql and utlpg.sql scripts in the Oracle database <code>%ORACLE_HOME%\rdbms\admin</code> directory, in the following order, to upgrade their respective package specifications:

```
C:\> cd %ORACLE_HOME%\rdbms\admin
SQL> @utlraw.sql
SQL> @utlpg.sql
```

Step 2: Repeat installation of UTL_RAW and UTL_PG package body

After the scripts have run, repeat Steps 1a and 1b in Upgrading or Migrating the Oracle Database from Previous Gateways and then, proceed to Upgrading PGAU from Previous Gateway Releases.



TIPs and dependent client applications must be recompiled after reinstallation of the package specifications. Refer to *Oracle Database Gateway for APPC User's Guide* for more information about compiling TIPs

9.4.2 Upgrading PGAU from Previous Gateway Releases

Upgrade the PG DD as follows before execution the new PGAU:

- **1.** If necessary, then use SQL*Plus to connect to the Oracle database as user PGAADMIN.
- 2. From SQL*Plus, run the pgddupgr.sql script in the %ORACLE_HOME% \dg4appc\admin directory. This script upgrades the PG DD.

```
C:\> cd %ORACLE_HOME%\dg4appc\admin
SQL> @pgddupgr.sql
```

9.5 Optional Configuration Steps to Permit Multiple Users

The following configuration steps are optional. Perform these steps if you want to allow users other than PGAADMIN to perform PG DD operations using PGAU.

1. Create public synonyms for the PG DD to allow other users to access the tables:



- a. Use SQL*Plus to connect to the Oracle database as user SYSTEM.
- b. From SQL*Plus, run the pgddcr8s.sql script in the %ORACLE_HOME%\dg4appc\admin directory. This script creates public synonyms for the PG DD.

```
C:\> cd %ORACLE_HOME%\dg4appc\admin
SQL> @pgddcr8.sql
```

- 2. Create roles for accessing the PG DD, performing definitions of transactions, and generating TIP specifications. The PGAADMIN user can grant these roles to other users as necessary.
 - a. Use SQL*Plus to connect to the Oracle database as user PGAADMIN.
 - b. From SQL*Plus, run the pgddcr8r.sql script in the %ORACLE_HOME%\dg4appc\admin directory. This script creates two roles, PGDDDEF and PGDDGEN. The PGDDDEF role provides SELECT, INSERT, UPDATE, and DELETE privileges against some of the PG DD tables, and select privileges against others, and allows execution of the PGAU DEFINE, GENERATE, REDEFINE, REPORT, and UNDEFINE statements. The PGDDGEN role provides select privileges against the PG DD tables, and allows execution of the PGAU GENERATE and REPORT statements only.

```
C:\> cd %ORACLE_HOME%\dg4appc\admin
SQL> @pgddcr8r.sql
```

3. Grant access to PGA required packages.

TIP developers require access to the following PL/SQL packages, which are shipped with the Oracle database :

- DBMS PIPE in the %ORACLE HOME%\rdbms\admin directory
- UTL RAW in the %ORACLE HOME%\rdbms\admin directory
- UTL PG in the %ORACLE HOME%\rdbms\admin directory

Explicit grants to execute these packages must be made to TIP developers.

These grants can be private, as in the following example:

```
C:\> sqlplus SYS\pw@database_specification_string
SQL> GRANT EXECUTE ON UTL_RAW TO tip_developer;
SQL> GRANT EXECUTE ON UTL_PG TO tip_developer;
SQL> GRANT EXECUTE ON DBMS_PIPE TO tip_developer;
SQL> CONNECT PGAADMIN\pw@database_specification_string
SQL> GRANT EXECUTE ON PGAADMIN.PURGE_TRACE TO tip_developer;
SQL> GRANT EXECUTE ON PGAADMIN.READ_TRACE TO tip_developer;
SQL> GRANT EXECUTE ON PGAADMIN.GPGLOCAL TO tip_developer;
SQL> exit
```

Alternatively, these grants can be public, as in the following example:

```
C:\> sqlplus SYS\pw@database_specification_string
SQL> GRANT EXECUTE ON UTL_RAW TO PUBLIC;
SQL> GRANT EXECUTE ON UTL_PG TO PUBLIC;
SQL> GRANT EXECUTE ON DBMS_PIPE to PUBLIC;
SQL> CONNECT PGAADMIN\pw@database_specification_string
SQL> GRANT EXECUTE ON PGAADMIN.PURGE_TRACE TO PUBLIC;
SQL> GRANT EXECUTE ON PGAADMIN.READ_TRACE TO PUBLIC;
SQL> GRANT EXECUTE ON PGAADMIN.GPGLOCAL TO PUBLIC;
SQL> EXIT
```



You can use either private or public grants. Both are sufficient for using PGA. Public grants are easier and can be performed now. If you use private grants, then they must be issued each time a new TIP developer user ID is created.

SQL scripts for performing these grants are provided in the %ORACLE HOME% \dq4appc\admin directory. The pgddapub.sql script performs these grants for public access to the packages. The pgddadev.sql script performs the grants for private access to the packages by a single TIP developer. If you are going to use private grants, then you must run the pgddadev.sgl script once for each TIP developer's user ID:

- a. Use SQL*Plus to connect to the Oracle database as user PGAADMIN.
- b. From SQL*Plus, run the suitable script (pgddapub.sql or pgddadev.sql) from the <code>%ORACLE HOME%\dg4appc\admin directory</code>. The script performs the necessary grants as described earlier. You are prompted for the required user IDs, passwords, and database specification strings. If you are using private grants, then repeat this step for each user ID requiring access to the packages.

```
C:\> cd %ORACLE HOME%\dg4appc\admin
SQL> @pqddapub.sql
or
SQL> @pgddadev.sql
```

4. If you are upgrading from a previous release of the gateway when the communication protocol was SNA, to the current gateway using TCP/IP, and if you want to upgrade your existing TIPs with new function and maintenance, then regenerate existing TIP specifications using the PGAU GENERATE statement.

Note:

The Procedural Gateway Administrative Utility (PGAU) has been enhanced to automatically upgrade existing PG DD entries with a new attribute when a PGAU GENERATE command is executed. To support this enhancement, add a new privilege to the PGDDGEN role. To do this, as the PGAADMIN user, use SQL*Plus to connect to the Oracle database where the PG DD is stored. Then, issue the following SQL command:

SQL> GRANT INSERT ON PGA DATA VALUES TO PGDDGEN

a. Call PGAU in the directory path where the PGAU control files are generated and where TIPs are stored:

```
C:\> pgau
PGAU> CONNECT PGAADMIN\pgaadmin@database specification string
PGAU> GENERATE tranname
PGAU> EXIT
```

For more information about the GENERATE command, refer to the PGAU GENERATE section in Chapter 2 of the Oracle Database Gateway for APPC User's Guide.

Note that it is not necessary to define the PG DD entries again.



5. Call SQL*Plus in the same directory path where the newly-generated TIP specifications are stored.

```
C:\> sqlplus tip_owner\pw@database_specification_string
SQL> @tipname.pkh
SQL> @tipname.pkb
SOL> exit
```

PGAU GENERATE produces the TIP in two output files, a specification and a body. You must compile both, first the specification and then the body.

For more information about the GENERATE command, refer to the PGAU GENERATE command section in Chapter 2 of the *Oracle Database Gateway for APPC User's Guide*.

9.6 Configuring TCP/IP for the Gateway

You must now configure the TCP/IP for IMS Connect communication package profiles for TCP/IP connections.

Configure the profiles to define the TCP/IP conversations with the OLTP.

When you have finished configuring your communications package, return to the following section, Configuring the Gateway.

9.7 Configuring the Gateway

Use the following steps to configure the gateway.

Customize the gateway parameters.

There are a number of parameters specific to the Oracle Database Gateway for APPC when it is using TCP/IP for IMS Connect. These are supplied in the gateway parameter file, initsid.ora, which is in the <code>%ORACLE_HOME%\dg4appc\admin</code> directory. A sample gateway parameter file, initPGA.ora, is provided in this subdirectory.



In the initsid.ora file, substitute your gateway SID name for "sid" in this file name.

The initsid.ora file contains both APPC and TCP/IP parameters, separated by a description. You must modify the <code>initsid.ora</code> file by deleting the APPC parameters. Refer to Gateway Initialization Parameters for TCP/IP Communication Protocol for the valid TCP/IP parameters.

The parameters fall into two categories:

gateway initialization parameters

These parameters control the general operation of the gateway in the Oracle environment.



Note:

Before performing the following step, refer to Gateway Initialization Parameters for TCP/IP Communication Protocol for information about tailoring gateway initialization and PGA parameters. Pay special attention to the information about using the PGA_CAPABILITY parameter.

PGA parameters

PGA parameters control the TCP/IP interface portion of the gateway. Use the SET gateway initialization parameter to specify PGA parameters. Oracle recommends that you group all SET commands for PGA parameters at the end of the initsid.ora file.

Note:

Misspelled parameters are ignored. However, if the <code>%ORACLE_HOME%</code> \dg4appc\admin\initsid.ora file is missing, then all calls to the gateway fail and return a PGA-20928 error.

9.8 Loading the PGA_TCP_IMSC Table

Gateway users who wish to employ the TCP/IP protocol do so by using the pg4tcpmap tool.

The pg4tcpmap tool resides on the gateway. Its function is to map the side profile name to TCP/IP and IMS Connect attributes. You must run this tool before executing the PL/SQL gateway statements (such as $ORACLE_HOME\%$

\dg4appc\demo\IMS\pgaims.sql).

In PGAINIT TIP, for example, the user must specify a side profile name. The SNA protocol recognizes and uses the parameter. In this release of the gateway, the pg4tcpmap tool uses the original PGAINIT TIP format to map the relevant SNA parameters to TCP/IP. The pg4tcpmap tool inserts the values of these parameters into a table called PGA_TCP_IMSC.

Before executing pg4tcpmap, you must specify the ORACLE_HOME, Oracle SID and modify initsid.ora. Refer to Gateway Initialization Parameters for TCP/IP Communication Protocol in this guide and Chapter 6 in the *Oracle Database Gateway* for APPC User's Guide for complete information about the pg4tcpmap commands.

Chapter 6 of the *Oracle Database Gateway for APPC User's Guide* contains a list of pg4tcpmap commands and instructions for using them, as well as an example of the table. Refer to "Troubleshooting" in the *Oracle Database Gateway for APPC User's Guide* for information about the trace file for the executed pg4tcpmap tool.

To operate this tool, execute the following command:

C:\> cd %ORACLE_HOME%\bin
C:\> pg4tcpmap



Refer to "Output for the pg4tcpmap Tool" for a sample of the pg4tcpmap output.

9.9 Verifying the Gateway Installation and OLTP Configuration

To verify the gateway installation and the OLTP configuration, perform the following procedures after installing the gateway.



If your database link name is not "PGA," modify the demonstration <code>.sql</code> files to give them the particular database link name that you created in Step <code>#unique_145/unique_145_Connect_42_i1008586</code> of "Configuring the Oracle Database: First Time Installation". You must modify the following <code>.sql</code> files:

- pgavsn.sql
- · pgaecho.sql
- pgaims.sql

9.9.1 Verifying the Gateway Installation

To verify the gateway software installation using the database link PGA previously created, perform the following steps:

- 1. Using SQL*Plus, connect to your Oracle database as user PGAADMIN.
- 2. Run %ORACLE HOME%\dg4appc\demo\pgavsn.sql.

```
C:\> cd %ORACLE_HOME%\dg4appc\demo
SQL> @pgavsn.sql
```

The server version number banner appears at your terminal. You will receive the following output:

```
Oracle Database Gateway for APPC (extension TCP/IP for IMS connect). Version 11.2.0.0.2 Thu Jun 11 14:52:36 2009

Copyright (c) Oracle Corporation 1979, 2009. All rights reserved.
```

PL/SQL procedure successfully completed.

3. Run %ORACLE HOME%\dg4appc\demo\pgaecho.sql.

```
C:\> cd %ORACLE_HOME%\dg4appc\demo
SQL> @pgaecho.sql
```

You will receive the following output:

```
==> Congratulations, your installation was successful. <==
```



9.9.2 Verifying the OLTP Configuration

Use the following procedure to verify the OLTP configuration.



If you have not completed the file transfers detailed in "Preparing to Configure a Gateway Installation/Upgrade",then complete them now, before proceeding to the next step.

9.9.2.1 IMS/TM Verification

Perform the following steps to verify the IMS/TM configuration. Be certain that you have installed and configured the IMS Connect and that it is up and running before you begin this procedure. Refer to the IBM *IMS Connect Guide and Reference* for information about how to perform the installation and configuration tasks.



TIPs must be recompiled when changing the communication protocol to TCP/IP.

TCP/IP only: If you have existing TIPs that were generated previously on a gateway using the SNA protocol and you want to use the new TCP/IP feature, then the TIPs will have to be regenerated by PGAU with mandatory NLS_LANGUAGE and Side Profile Settings. Specify the suitable ASCII character set in the DEFINE TRANSACTION command.

This is because the gateway assumes that the appropriate user exit in IMS Connect is being used, which would translate between the suitable ASCII and EBCDIC character sets.

1. To verify that the FLIP transaction is installed correctly, log on to your IMS/TM system and enter the following transaction (replacing FLIP with the transaction ID you chose for FLIP when you configured the IMS/TM system for the gateway):

FLIP THIS MESSAGE

The following output appears on your terminal:

EGASSEM SIHT PILF





If you have not completed the file transfers detailed in Preparing to Configure a Gateway Installation/Upgrade "Preparing to Configure a Gateway Installation/Upgrade", then complete them now, before proceeding to the next step.

- 2. From your Windows platform, modify the pgaims.sql file, which resides at %ORACLE_HOME%\dg4appc\demo\IMS\pgaims.sql. Customize the following three items used for accessing the gateway and the IMS/TM system, as described in the comments at the beginning of the file:
 - the IMS/TM transaction ID
 - the side profile name
 - the logmode entry name
- 3. Ensure that the TCP/IP communication protocol on your system has been started.
- 4. Using SQL*Plus, connect to your Oracle database from PGAADMIN.
- 5. Run pgaims.sgl.

```
C:\> cd %ORACLE_HOME%\dg4appc\demo\IMS
SQL> @pgaims.sql
```

The following message appears:

```
==> Congratulations, your gateway is communicating with IMS/TM <==
```

Your IMS/TM installation verification is now complete.

9.10 Performing Postinstallation Procedures

The following are optional steps that you can perform as necessary. Installation of the sample applications for the OLTP is recommended to help you to fully understand how the gateway works and how it interfaces with the OLTP.

9.10.1 Installing Sample Applications

Your Oracle Database Gateway for APPC featuring TCP/IP for IMS Connect contains sample PL/SQL procedures and OLTP transaction programs that demonstrate the gateway's capabilities.



Note:

When you are calling a gateway that is using TCP/IP as the communication protocol, and you are using EBCDIC as the language in the control files, you must change the language from EBCDIC to ASCII. Some examples of control files that may be in EBCDIC language are ivtno.ctl and ivtnv.ctl.

For more information, refer to the <code>%ORACLE_HOME%</code> \dg4appc\demo\IMS\ivtno.ctl and \%ORACLE HOME%\dg4appc\demo\IMS\ivtnv.ctl files.

Samples are provided for IMS/TM:

IMS inquiry using IVTNO and IVTNV sample transactions

Additional samples are added to the distribution media in later releases of the product. Wherever possible, the sample applications use the sample databases provided with the database products.

For this release, full documentation on installing and using the sample applications is available in the README.doc files in the following directory:

%ORACLE HOME%\pg4appc\demo\IMS\sample IMS applications.txt



10

Security Requirements

The gateway architecture involves multiple systems, database servers, and communications facilities, each having distinct security capabilities and limitations. To effectively plan and implement your security scheme, you must understand these capabilities and limitations, in addition to knowing your installation's security requirements.

Read the following topics to learn about the capabilities and limitations of the Oracle Database Gateway for APPC:

- Overview of Security Requirements
- Authenticating Application Logons
- · Defining and Controlling Database Links
- Using SNA Security Validation
- TCP/IP Security
- · Passwords in the Gateway Initialization File

10.1 Overview of Security Requirements

Before implementing the security scheme, you must understand the existing security requirements and expectations in the environment. Because you are enabling application access to different databases on different systems, you must merge multiple security cultures. When developing your security scheme, the most stringent security requirements prevail. When you connect different systems into an operating whole, the system with the strictest security requirements generally dictates what the other systems can and cannot do.

Gateway security includes two main concerns:

- users and applications that are permitted access to a particular gateway instance and OLTP
- OLTP transactions that users and applications are able to execute

You can control access at several points in the gateway architecture. The primary options are discussed in the following sections. Control over remote transaction program (RTP) access is provided by each OLTP with native authorization mechanisms based on user ID. These facilities are described in the product documentation for your OLTP. Information in the following topics include how the gateway facilities determine the user ID that is in effect for a particular OLTP connection.

When the gateway is involved in an RPC request, security mechanisms are in effect for each system component encountered by the gateway. The first system component that is encountered is the application tool or 3GL program. The last system component that is encountered is the OLTP.

Each of the following sections identifies the component and the type of security processing that is available in that component. Each section offers a summary of key features and parameters. Refer to product-specific documentation for detailed information about the non-gateway components for Oracle and non-Oracle products.

10.2 Authenticating Application Logons

An application must connect to an Oracle database before using that gateway. The type of logon authentication that you use determines the resulting Oracle user ID and can affect gateway operation.

Two basic types of authentication are available:

Oracle authentication.

With Oracle authentication, each Oracle user ID has an associated password that is known to Oracle. When an application connects to the server, it supplies a user ID and password. Oracle confirms that the user ID exists and that the password matches the one stored in the database.

· Operating system authentication

With operating system authentication, the server's underlying operating system is responsible for authentication. An Oracle user ID that is created with the IDENTIFIED EXTERNALLY attribute (instead of a password) is accessed with operating system authentication. To log on to such a user ID, the application supplies a slash (/) for a user ID and does not supply a password.

To perform operating system authentication, the server determines the requester's operating system user ID, optionally adds a fixed prefix to it, and uses the result as the Oracle user ID. The server confirms that the user ID exists and is identified externally, but no password checking is done. The underlying assumption is that users were authenticated when they logged on to the operating system.

Operating system authentication is not available on all platforms and is not available in some Oracle Net (client-server) and multi-threaded server configurations. Refer to your Windows Oracle database documentation and *Oracle Database Net Services Administrator's Guide* to determine the availability of this feature in your configuration.

For more information about authenticating application logons, refer to the *Oracle Database Administrator's Guide*.

10.3 Defining and Controlling Database Links

These topics discuss database links for users of the gateway employing either TCP/IP or SNA communications protocols.

- Link Accessibility
- Links and CONNECT Clauses

10.3.1 Link Accessibility

The first point of control for a database link is whether it is accessible to a given user. A public database link can be used by any user ID. A private database link can be used only by the user who created it. Database link usability is determined by its ability to open a session to the gateway. The Oracle database makes no distinction as to the type of use (such as read-only and update or write) or which remote objects can be accessed. These distinctions are the responsibility of the OLTP that is accessed.



10.3.2 Links and CONNECT Clauses

The CONNECT clause is another security-related attribute of a database link. You can use the CONNECT clause to specify an explicit user ID and password, which can differ from the user's Oracle user ID and password. This CONNECT user ID and password combination is sent to the gateway when the database link connection is first opened. Depending on gateway-specific options, the gateway might send that user ID and password to the OLTP to be validated.

If a database link is created without a CONNECT clause using Oracle authentication, then the user's Oracle user ID and password are sent to the gateway when the connection is opened. If the user logs on to the Oracle database with operating system authentication, then the gateway receives no user ID or password from the Oracle database. It is impossible for operating system-authenticated Oracle users to use a gateway database link defined without a CONNECT clause. However, if your OLTP provides user ID mapping facilities based on the gateway LU name from which the user is connecting, then such a connection is possible if all users on the same gateway instance can use the same OLTP user ID.

For more information about database links, refer to the *Oracle Database Administrator's Guide*.

10.4 Using SNA Security Validation

The information in this section applies only to the security needs of gateway users employing the SNA communications protocol. When an RPC request to start a remote transaction program is received by the gateway, the gateway attempts to start an APPC conversation with the OLTP. Before the conversation can begin, a session must start between Windows' Logical Unit (LU) and the OLTP LU.

APPC support for the Windows platform is provided by the SNA Server (Microsoft Host Integration Server or IBM Communication Server v6.1.1 or higher).

SNA and its various access method implementations, including VTAM and the SNA Server, provide security validation at session initiation time, allowing each LU to authenticate its partner. This validation is carried out entirely by network software before the gateway and OLTP application programs begin their conversation and process conversation-level security data. If session-level security is used, then correct password information must be established in Microsoft Windows' SNA profiles and in similar parameter structures in the OLTP to be accessed. Refer to the suitable communications software product documentation for detailed information about this subject.

10.4.1 Specifying SNA Conversation Security

The PGA_SECURITY_TYPE parameter of the gateway initialization file allows you to specify one of three options that determine the security conduct of the LU6.2 conversation that is allocated with the OLTP. These options are part of the SNA LU6.2 architecture, but their precise behavior might vary depending on the particular OLTP system.

10.4.1.1 SNA Security Option SECURITY=NONE

If you specify PGA_SECURITY_TYPE=NONE, then the gateway performs no processing of the client user ID and password. The conversation is allocated with SNA option SECURITY=NONE.



10.4.1.2 SNA Security Option SECURITY=PROGRAM

If you specify PGA_SECURITY_TYPE=PROGRAM, then the gateway allocates the conversation with SNA option SECURITY=PROGRAM, and the following information is sent to the OLTP:

- If the TIP user ID and password overrides are used, then the specified user ID and password are sent regardless of the database link specification.
- If the database link has explicit CONNECT information, then the specified user ID and password are sent.
- If the database link has no CONNECT clause, and if the application logged on to
 Oracle with an explicit user ID and password, then the Oracle user ID and
 password are sent.
- If the application logs on to Oracle with operating system authentication, and if the
 database link lacks explicit CONNECT information, then no user ID and password are
 sent. If no user ID and password are sent, and if the OLTP is not configured to
 assign a default user ID, then the connection fails.

In general, SNA option SECURITY=PROGRAM tells the OLTP to authenticate the user ID/ password combination using whatever authentication mechanisms are available. For example, if CICS Transaction Server for z/OS is the OLTP, then RACF can be used. This is not always the case, however, because each OLTP can be configured to process inbound user IDs in other ways.

10.5 TCP/IP Security

The security information in this section applies only to users of the Oracle Database Gateway for APPC using the TCP/IP for IMS Connect feature. When an RPC request to start a RTP is received by the gateway, the gateway attempts to start the TCP/IP conversation with IMS Connect. IMS Connect would contact the OLTP (IMS) through OTMA and XCF. Refer to the IBM IMS Connect Guide and Reference for more information. The conversation between the gateway and IMS Connect occurs when the network uses the TCP/IP address or host name and port number to connect from the gateway to IMS Connect.

Note:

Because the gateway is using PGAU to generate TIPs, the TIPs contain SNA information. When using the Oracle Database Gateway for APPC with TCP/IP support for IMS Connect, you need to map the SNA names to the TCP/IP host name and port number in order for the gateway to communicate with IMS Connect. Use the pg4tcpmap tool to map the information from SNA to TCP/IP. Refer to Chapter 6, "pg4tcpmap Commands," of the *Oracle Database Gateway for APPC User's Guide* for more information.

IMS Connect provides validation at session initiation time, allowing each connection to authenticate its partner. This validation is carried out entirely by network software before the gateway and OLTP application programs at IMS begin their conversation and process conversation-level security data. If session-level security is used, then



correct password information must be established in Microsoft Windows and in similar parameter structures in the OLTP to be accessed.

10.5.1 Specifying TCP/IP Conversation Security

The PGA_SECURITY_TYPE parameter of the gateway initialization file allows you to specify the security conduct for the conversation that is allocated by the gateway for OLTP. Refer to Gateway Initialization Parameters for TCP/IP Communication Protocol .

10.5.1.1 TCP/IP Security Option SECURITY=NONE

If you specify $PGA_SECURITY_TYPE=NONE$, then the gateway performs no processing of the client user ID and password.

10.5.1.2 TCP/IP Security Option SECURITY=PROGRAM

If you specify PGA_SECURITY_TYPE=PROGRAM, then the following information is sent to the OLTP:

- If the TIP user ID and password overrides are used, then the specified user ID and password are sent regardless of the database link specification.
- If the database link has explicit CONNECT information, then the specified user ID and password are sent.
- If the database link has no CONNECT clause, and if the application logged on to Oracle with an explicit user ID and password, then the Oracle user ID and password are sent.
- If the application logs on to Oracle with operating system authentication, and if the database link lacks explicit CONNECT information, then no user ID and password are sent. If no user ID and password are sent, and if the OLTP is not configured to assign a default user ID, then the connection fails.

RACF is the only authentication mechanism available when the Oracle Database Gateway for APPC using TCP/IP for IMS Connect communicates with IMS Connect.



You must specify your RACF group name through the pg4tcpmap tool if you have set your PGA security option to SECURITY=PROGRAM. For more information about this issue, refer to the *Oracle Database Gateway for APPC User's Guide*.

10.6 Passwords in the Gateway Initialization File

Initialization parameters may contain sensitive information, such as user IDs or passwords. Initialization parameters are stored in plain text files and may be deemed insecure. An encryption feature has been added to Heterogenous Services making it possible to encrypt parameters values. This is done through the dg4pwd utility.





Refer to *Oracle Database Heterogeneous Connectivity User's Guide* for more information about this utility



11

Migrating from Existing Gateways

Migrating to new instances of the Oracle Database Gateway for APPC from an existing installation is straightforward, provided you follow some guidelines. The following topics provide information to make these new installations as easy as possible. They also provide the parameters you will need if you are using the TCP/IP for IMS Connect communication protocol on your gateway.

- Migrating an Existing Gateway Instance to New Release Using SNA Protocol
- Migrating from an Existing Gateway Using SNA to TCP/IP

11.1 Migrating an Existing Gateway Instance to New Release Using SNA Protocol

Follow these steps to migrate an existing gateway to 12c Release 2 (12.2) of the gateway using the SNA communication protocol.

Note that if you are using the gateway's TCP/IP support for IMS Connect, you will not be migrating an existing release to the current release of the gateway. However, you will need to place valid Heterogeneous Services parameters into your initsid.ora file. Proceed to "Parameter Changes: Version 4 to 12c Release 2 (12.2) of the Gateway".

11.1.1 Step 1: Install the New Release

Install the new release of the gateway in a separate directory as outlined in Installing the Gateway.



Do not install the gateway over an existing gateway installation. Doing so will corrupt the existing installation.

11.1.2 Step 2: Transfer initsid.ora Gateway Initialization File Parameters

Copy the initsid.ora file from the old gateway instance to the new instance.

Note that if you are migrating from Release 9.0.1 or earlier of the gateway, then PGA_TRACE is not supported, you will need to modify the parameter to TRACE_LEVEL, instead.



If you are using TRACE_LEVEL, then you must set the path for the LOG_DESTINATION parameter.

11.1.3 Backout Considerations When Migrating to New Releases

Oracle recommends that you keep the old gateway Oracle home directory and instance configurations intact and operational when you are installing a new release of the gateway and upgrading existing instances, in case there are problems with the upgrade. This will help ensure minimal downtime between changes to different gateway instances.

11.1.4 Oracle Net Considerations

The Oracle Database Gateway for APPC uses the Heterogeneous Services (HS) facilities of Oracle and Oracle Net. If you are upgrading from a version 4 gateway, then you need to slightly modify the gateway service name entries in the tnsnames.ora file. Add an (HS=) clause to communicate to Oracle Net that the gateway uses HS facilities. For more information, refer to Configuring Your Oracle Network .

11.1.5 Parameter Changes: Version 4 to 12c Release 2 (12.2) of the Gateway

This release of the Oracle Database Gateway for APPC introduces new and changed initialization parameters if you are migrating from version 4 gateway to 12c Release 2 (12.2) of the gateway.



This section does not apply to you if you are migrating to 12c Release 2 (12.2) from version 8 of the Oracle Database Gateway for APPC.

If you are using the gateway's TCP/IP support for IMS Connect, then you will not be migrating from version 4 to the current release of the gateway. However, you will need to place valid Heterogeneous Services parameters into your initsid.ora file.

The following topics contain references to the particular HS parameters you need to run the gateway.

Note:

Refer to the *Oracle Database Heterogeneous Connectivity User's Guide* for a complete list and descriptions of all HS parameters used in Oracle products.



New Gateway Initialization Parameters

The following parameters are in the gateway initialization file (initsid.ora):

- FDS CLASS
- FDS INSTANCE
- HS FDS FETCH ROWS
- LOG DESTINATION
- TRACE LEVEL
- PGA TCP DB (TCP/IP only)
- PGA TCP USER (TCP/IP only)
- PGA TCP PASS (TCP/IP only)

Note:

The HS_ parameters are specific to Oracle Heterogeneous Services. For details on HS parameters, refer to the *Oracle Database Administrator's Guide*.

Renamed Gateway Initialization File Parameters

Following is a list of the gateway initialization file (initsid.ora) parameters that have been renamed in this release of the gateway, the parameters' former names are shown in parentheses.

- HS COMMIT STRENGTH POINT (COMMIT STRENGTH POINT)
- HS DB DOMAIN (DB DOMAIN)
- HS DB INTERNAL NAME (DB INTERNAL NAME)
- HS DB NAME (DB NAME)
- HS DESCRIBE CACHE HWM (DESCRIBE CACHE HWM)
- HS LANGUAGE (LANGUAGE)
- HS NLS DATE FORMAT (NLS DATE FORMAT)
- HS NLS DATE LANGUAGE (NLS DATE LANGUAGE)
- HS OPEN CURSORS (OPEN CURSORS)
- HS ROWID CACHE SIZE (ROWID CACHE SIZE)

Obsolete Parameters

The following parameters are now obsolete. Please remove them from your configuration files:

- MODE
- SERVER PATH
- ERROR LOGGING



- ERROR REPORTING
- ERRORTAG
- GATEWAY SID
- GROUP BY OFF
- GTWDEBUG
- INCREMENT CURSORS
- INIT CURSORS
- LIST
- MAX LOG SIZE
- OPTIMIZE FILE OPEN
- ORDER BY OFF
- RESOLVE BINDS
- RETRY
- SET
- SNMP SUPPORT
- SQL_TRACE
- TRIM CURSORS
- D OPEN CURSORS
- D INIT CURSORS
- D INCREMENT CURSORS
- D TRIM CURSORS
- PGA_TRACE

11.1.6 Parameter Changes: Version 8 or Earlier to Gateway 12*c* Release 2 (12.2)

The following startup shell script parameter must be added to initsid.ora if you are migrating from version 4 or version 8 gateway to the current release of the Oracle Database Gateway for APPC:

FDS_CLASS_VERSION

11.1.7 Migrating from Gateway Release 9.0.1 or 9.2.0 to Gateway 12c Release 2 (12.2)

No new parameters were added between release 9.0.1 and this release of the gateway.



11.2 Migrating from an Existing Gateway Using SNA to TCP/IP

The following sections are for users who have an existing release of the gateway using the SNA protocol but who wish to switch to using TCP/IP support for IMS Connect.

The TCP/IP support for IMS Connect feature in this release of the gateway allows you to continue to use existing TIPs.

11.2.1 To Use Existing TIPs with Existing Side Profile Definitions

Follow these instructions:

1. Make sure you have used the pg4tcpmap tool to insert valid parameter values into the PGA TCP IMSC table.

Refer to Gateway Configuration Using TCP/IP Communication Protocol for instructions on loading the PGA TCP IMSC table.

- 2. Make sure that the LANGUAGE parameter in your TIPs is set to american america us7ascii.
- 3. Use PGAU to regenerate the IMS TIPs.
- **4.** Add the following new TCP/IP parameters to the initsid.ora file:
 - PGA TCP DB
 - PGA TCP USER
 - PGA TCP PASS

You will find descriptions and information about adding these parameters in Parameter Changes: Version 4 to 12c Release 2 (12.2) of the GatewayParameter Changes: Version 4 to 12c Release 2 (12.2) of the Gateway. You will also find descriptions of the parameters in Gateway Initialization Parameters for TCP/IP Communication Protocol .

Note:

If your TIPs from a previous version of the gateway were already defined using a side profile name and the NLS_LANGUAGE parameter has been set to a value of american_america_us7ascii, then you will not need to recompile these TIPs. You will still need to map your parameter values using the pg4tcpmap tool.



Note:

TIPS must be recompiled when changing the communication protocol from SNA to TCP/IP.

If you have existing TIPs that were generated previously on a gateway using the SNA protocol and you want to use the new TCP/IP feature, then the TIPs will have to be regenerated by PGAU with mandatory <code>NLS_LANGUAGE</code> and Side Profile Settings. Specify the suitable ASCII character set in the <code>DEFINE TRANSACTION</code> command.

This is due to the fact that the gateway assumes that the suitable user exit in IMS Connect is being used, which would translate between the suitable ASCII and EBCDIC character sets.



A

Gateway Initialization Parameters for SNA Protocol

This topic describes the gateway initialization file location and lists the gateway initialization parameters supported by the Oracle Database Gateway for APPC specifically for the SNA protocol. These parameters are fully documented in Migrating an Existing Gateway Instance to New Release Using SNA ProtocolMigrating an Existing Gateway Instance to New Release Using SNA Protocol. In addition, the following topic contains sample listener.ora and tnsnames files for a gateway using SNA.

The parameter file for the gateway is located in the <code>%ORACLE_HOME%\dg4appc\admin</code> directory and is called <code>initsid.ora</code>.



The initsid.ora file contains both SNA and TCP/IP parameters. You must modify these files with the suitable parameters.

A.1 PGA Parameters

The PGA parameters control the APPC interface portion of the gateway.

PGA parameters are specified using the SET gateway initialization parameter. For example:

SET pga_parm=value

where:

- pga parm is one of the PGA parameter names in the list that follows; and
- value is a character string with contents that depend on pga parm

Table A-1 provides a list of PGA parameters and their descriptions.

Table A-1 PGA Parameters for Oracle Database Gateway for APPC Using SNA

Parameter	Description
LOG_DESTINATION=logpath	$logpath$ specifies the destination at which STDERR is reopened. LOG_DESTINATION specifies a directory only and STDERR is reopened to logpath\ sid_pid .log
	where:
	• sid is the sid name
	 pid is the process ID assigned to the gateway



Table A-1 (Cont.) PGA Parameters for Oracle Database Gateway for APPC Using SNA

Parameter	Description
PGA_CAPABILITY	PGA transaction capability. This controls whether updates are allowed through the gateway. The following are valid values:
	READ_ONLY or RO, read-only capabilities.
	SINGLE_SITE or SS, single-site update only. This indicates that in a distributed environment, only the gateway can perform updates. No other database updates can occur within the Oracle transaction.
	COMMIT_CONFIRM or CC, commit-confirm. This indicates that in a distributed environment, updates can be performed by both the gateway and other participants within the Oracle transaction. The gateway is always committed first in this mode, and no other commit-confirm sites are allowed to participate in the Oracle transaction.
	The default is SINGLE_SITE.
PGA_CONFIRM	Incoming APPC CONFIRM request handling option. This controls what the gateway does when an APPC CONFIRM request is received from the remote transaction program (RTP). This parameter has meaning only when the conversation is running with SYNCLEVEL > 0. The following are valid values:
	ACCEPT - respond to incoming APPC CONFIRM requests with APPC CONFIRMED responses.
	REJECT - treat incoming APPC CONFIRM requests as errors causing the conversation to be deallocated and an error message to be issued.
	The default is REJECT.
PGA_LOG_DB	The Oracle Net service name for the Oracle database in which the gateway maintains its transaction log. This parameter can be from 1 to 255 characters long. This parameter is required only when PGA CAPABILITY parameter is set to COMMIT CONFIRM.
	There is no default value.
PGA_LOG_PASS	The Oracle password to be used by the gateway when connecting to the Oracle database specified by the PGA_LOG_DB parameter. The password can be from 1 to 30 characters long. This parameter is required only when PGA_CAPABILITY parameter is set to COMMIT_CONFIRM. The password can be encrypted. For more information about encrypting the password, refer to Passwords in the Gateway Initialization File. There is no default value.
PGA LOG USER	The Oracle user ID to be used by the gateway when connecting to
101, 100 00 10	the Oracle database specified by the PGA_LOG_DB parameter. The user ID can be from 1 to 30 characters long. This parameter is required only when PGA_CAPABILITY parameter is set to
	COMMIT_CONFIRM.



Table A-1 (Cont.) PGA Parameters for Oracle Database Gateway for APPC Using SNA

Parameter	Description
PGA_RECOVERY_PASS	The password to be used by the gateway when allocating an APPC conversation with the transaction specified by the PGA_RECOVERY_TPNAME parameter. The password can be from 1 to 8 characters long. This parameter is required only when PGA_CAPABILITY parameter is set to COMMIT_CONFIRM and PGA_SECURITY_TYPE parameter is set to PROGRAM. The password can be encrypted. For more information about encrypting the password, refer to Passwords in the Gateway Initialization File.
	There is no default value.
PGA_RECOVERY_TPNAME	The TP name of the transaction installed in the online transaction processor (OLTP) for commit-confirm FORGET and RECOVERY processing. The TP name can be from 1 to 64 characters long. For CICS Transaction Server for z/OS, the TP name is limited to four characters. For IMS/TM, the TP name is limited to eight characters. Other OLTPs might have other limits on the length of the TP name. This parameter is required only when PGA_CAPABILITY parameter is set to COMMIT_CONFIRM.
	The default value is RECO.
PGA_RECOVERY_USER	The user ID to be used by the gateway when allocating an APPC conversation with the transaction specified by the PGA_RECOVERY_TPNAME parameter. The user ID can be from 1 to 8 characters long. This parameter is required only when PGA_CAPABILITY parameter is set to COMMIT_CONFIRM and PGA_SECURITY_TYPE parameter is set to PROGRAM or SAME.
	There is no default value.
PGA_SECURITY_TYPE	APPC conversation security option. This controls what security parameters are sent to the OLTP in the FMH-5 at conversation allocation. The following are valid values:
	NONE, which sends no security parameters
	SAME, which sends only a user ID
	PROGRAM, which sends a user ID and password
	The default is NONE.
	For further information about these options, refer to Security Requirements .
TRACE_LEVEL	PGA trace level. This controls tracing output written to STDERR (the target of the LOG_DESTINATION parameter. The value must be an integer from 0 to 255.
	integer from 6 to 255.
	The default is 0, indicating no tracing.

A.2 PGA_CAPABILITY Parameter Considerations

When choosing a setting for the $PGA_CAPABILITY$ parameter, take care to ensure that the correct setting is used based on what the RTPs will be doing.

The READ_ONLY setting should always be used when the RTPs are read-only, that is, when the RTPs perform no database updates. READ_ONLY should never be used when the RTPs

perform database updates. For example, if the READ_ONLY setting is chosen, and if a RTP called by the gateway performs updates to a foreign database, then the Oracle database does *not* provide any integrity protection for those updates. Further, READ_ONLY mode allows a gateway transaction to be part of a distributed transaction that might update several other databases. If the gateway calls a RTP that performs updates in this situation and if a failure occurs, then the database updated by the RTP is out of sync with the other databases.

In cases where the RTPs perform updates to foreign databases, there are two options for PGA CAPABILITY:

- SINGLE SITE
- COMMIT CONFIRM

Each of these options provides protection against data integrity problems by permitting COMMIT and ROLLBACK requests to be forwarded to the RTP and by informing the Oracle database about the distributed update and recovery capabilities of the gateway. The particular option chosen depends on the design of the RTPs and upon the capabilities of the OLTP where they execute.

If the OLTP has LU6.2 SYNCLEVEL 1 or 2 support, then the COMMIT_CONFIRM capability provides limited two-phase commit between the Oracle database and the OLTP, with the restriction that no other commit-confirm site (gateway or Oracle) can be part of the distributed transaction. If it is not possible to use COMMIT_CONFIRM, then the SINGLE_SITE capability provides update capability between the Oracle database and the OLTP, with the restriction that only the OLTP can perform updates, and no updates can occur on the Oracle side.

Each of the PGA_CAPABILITY options for update control imposes specific requirements on the RTP and on the OLTP. For COMMIT_CONFIRM capability, these requirements are discussed in detail in Chapter 5, "Implementing Commit-Confirm," of the *Oracle Database Gateway for APPC User's Guide*. Also refer to Configuring the OLTP for Commit-ConfirmConfiguring the OLTP for Commit-Confirm in this guide. For SINGLE_SITE capability, the RTP is responsible for performing the suitable tasks in response to COMMIT and ROLLBACK requests received from the gateway on behalf of the Oracle database. The gateway uses the APPC CONFIRM and SEND_ERR requests to implement COMMIT and ROLLBACK, respectively. On receipt of a CONFIRM command, the RTP must perform COMMIT processing and then respond to the gateway with an APPC CONFIRMED response. On receipt of a SEND_ERR command, the RTP must perform ROLLBACK processing.

Because the distributed transaction capability of the Oracle database is affected by the PGA_CAPABILITY option used by the gateway, it is desirable to separate inquiry and update applications by using different gateway instances for each. One gateway can be defined with PGA_CAPABILITY set to READ_ONLY and others with PGA_CAPABILITY set to SINGLE SITE or COMMIT CONFIRM.

This allows read-only transaction programs to participate in distributed transactions under the control of the Oracle database . For example, data from DB2 can be retrieved through the <code>READ_ONLY</code> gateway by an inquiry-only RTP, and can then be used as input to database updates on the Oracle database , all in one Oracle transaction. A <code>SINGLE_SITE</code> gateway can be used only for accessing RTPs which perform updates to foreign databases outside the scope of control of the Oracle database . Data can be read from any databases accessible to the Oracle database , and that data can be used to perform updates through the gateway.



When it is necessary to update resources on both the Oracle side and the OLTP side, a COMMIT_CONFIRM gateway can be used, provided that the OLTP and the RTPs are set up to implement COMMIT_CONFIRM.

All that is necessary to set up multiple gateway instances is to set up the following for each instance:

- an entry in the listener.ora file defining the sid of the gateway instance
- an entry in the tnsnames.ora file defining an alias to be used to connect to the gateway instance defined in listener.ora
- a database link in the Oracle database that specifies the alias defined in the tnsnames.ora file in its USING parameter.

Note that the gateway instances can share one common directory structure and use the same executables.

For example, to set up two gateways, PGAI and PGAU (for inquiry and update use, respectively), the following steps are required:

- 1. Define entries in listener.ora for two sids, PGAI and PGAU.
- 2. Define two aliases in thinnames.ora that connect to the two new sids, PGAI and PGAU.
- Define two database links in the Oracle database, one connecting to PGAI and the other connecting to PGAU.
- 4. Finally, create the initialization files initPGAI.ora and initPGAU.ora.

In initPGAI.ora, set PGA_CAPABILITY to READ_ONLY, and in initPGAU.ora, set PGA_CAPABILITY to SINGLE_SITE or COMMIT_CONFIRM. Then, use the PGAI gateway for inquiry-only transactions, and use the PGAU gateway for update transactions.

The same steps can be used to set up additional gateway instances.

A.3 PGA_CONFIRM Parameter Considerations

When deciding upon the setting for the PGA_CONFIRM parameter, it is important to understand the effects of each setting. First, keep in mind that this parameter affects only those conversations running at SYNCLEVEL 1. The default setting, PGA_CONFIRM=REJECT, is suitable for most applications. With this setting, the gateway generates an error if a CONFIRM request is received from the remote transaction program. If you have a remote transaction that uses CONFIRM to verify that data was received by the gateway, then you must use PGA_CONFIRM=ACCEPT to allow the gateway to respond to those incoming CONFIRM requests with CONFIRMED responses. You must be aware that the gateway sends CONFIRM requests to the remote transaction when the Oracle application has issued a COMMIT request. In order for the COMMIT processing to work correctly, the remote transaction must be written to perform its local commit processing whenever a CONFIRM request is received from the gateway, and respond to the gateway with CONFIRMED after the commit processing has successfully completed. If an error occurs during commit processing, then the remote transaction must respond to the gateway with SEND ERR to indicate that the commit failed.

One special case for the use of PGA_CONFIRM=ACCEPT is with IMS/TM version 7. When using the implied APPC support that is provided by IMS/TM version 7, conversations that run at SYNCLEVEL 1 are handled differently than conversations that run at SYNCLEVEL 0. IMS/TM automatically generates CONFIRM requests after each APPC SEND when the conversation is at SYNCLEVEL 1. On the gateway side, if PGA_CONFIRM=ACCEPT is not specified, then the CONFIRM



requests sent by IMS/TM result in errors generated by the gateway. Using PGA_CONFIRM=ACCEPT alleviates this problem, allowing the gateway to respond to incoming CONFIRM requests with CONFIRMED responses. The only limitation with running this way is that the implied APPC support provided by IMS does not notify the application when a CONFIRM request is received from the gateway. This means that the gateway cannot use CONFIRM to implement COMMIT, thereby disabling the use of COMMIT/ROLLBACK to control updates on the IMS side of the conversation.

A.4 Sample listener.ora File for a Gateway Using SNA

```
(ADDRESS LIST =
        (ADDRESS=
          (COMMUNITY= TCP.world)
          (Host = bay)
          (PROTOCOL= TCP)
          (Port= 2621)
        (ADDRESS=
          (COMMUNITY= TCP.world)
          (Host = bay)
          (PROTOCOL= TCP)
          (Port = 2623)
  )
SID LIST LISTENER =
  (SID LIST =
    (SID DESC =
      (SID NAME = PGA)
      (ORACLE HOME = C:\oracle\pga\12.2)
      (PROGRAM = pg4asrv)
  )
```

A.5 Sample tnsnames.ora File for a Gateway Using SNA

B

Gateway Initialization Parameters for TCP/IP Communication Protocol

The following topics list and describes the parameters needed specifically for a gateway featuring the TCP/IP for IMS Connect communication protocol. They also provide a sample output of the pg4tcpmap tool. In addition, the following topics contain sample listener.ora and tnsnames.ora files for a gateway using TCP/IP.

- Gateway Initialization Parameter File Using TCP/IP
- Output for the pg4tcpmap Tool

B.1 Gateway Initialization Parameter File Using TCP/IP

The parameter file for the Oracle Database Gateway for APPC using TCP/IP for IMS Connect is located in the <code>%ORACLE HOME%\dg4appc\admin</code> directory and is called <code>initsid.ora</code>.



The initsid.ora file contains both SNA and TCP/IP parameters. You will need to modify these files with the appropriate parameters.

The Procedural Gateway Administration (PGA) parameters control the TCP/IP interface portion of the gateway.

PGA parameters are specified using the SET gateway initialization parameter. For example:

SET pga parm=value

where:

- pga_parm is one of the PGA parameter names in the list that follows
- value is a character string with contents that depend on pga parm

The following table provides a list of PGA parameters and their descriptions.

Table B-1 PGA Parameters for Oracle Database Gateway for APPC Using TCP/IP for IMS Connect

Parameter	Description
LOG_DESTINATION=logpa th	$logpath$ specifies the destination at which STDERR is reopened. LOG_DESTINATION specifies a directory only, and STDERR is reopened to logpath\ sid_pid .log
	where:
	• sid is the sid name
	 pid is the process ID assigned to the gateway
	NOTE: This parameter will be used for the pg4tcpmap tool when you set your Trace Level to 255. The log file for this tool will reside in the same place as the gateway log file, in pg4tcpmap_sid.log.
PGA_CAPABILITY	PGA transaction capability. The following are valid values: READ_ONLY or RO: read-only capabilities.
	SINGLE_SITE or SS: single-site update only. This indicates that in a distributed environment, only the gateway can perform updates. No other database updates can occur within the Oracle transaction.
	The default is SINGLE_SITE.
PGA_SECURITY_TYPE	TCP/IP conversation security option. This controls what security parameters are sent to the OLTP. The following are valid values:
	NONE, which sends no security parameters
	PROGRAM, which sends a user ID and password
	The default is NONE.
	For further information on these options, refer to Security Requirements .
	Important: You must specify your RACF group name through the pg4tcpmap tool if you have set your PGA security option to SECURITY=PROGRAM. For more information about this issue, refer to the Oracle Database Gateway for APPC User's Guide.
	If you have already loaded the table PGA_TCP_IMSC and you did not first specify the RACF group name, then delete the row and reinsert it with the value for the RACF group name.
PGA_TCP_DB	The Oracle Net service name for the Oracle database in which the gateway receives its TCP/IP for IMS Connect information, such as host name and port number. This parameter can be from 1 to 255 characters long. This parameter is required.
	There is no default value.
PGA_TCP_PASS	The Oracle password to be used by the gateway when connecting to the Oracle database specified by the PGA_TCP_DB parameter. The password can be from 1 to 30 characters long. This parameter is required. The password can be encrypted. For more information about encrypting the password, refer to Passwords in the Gateway Initialization File.
	There is no default value.



Table B-1 (Cont.) PGA Parameters for Oracle Database Gateway for APPC Using TCP/IP for IMS Connect

D	
Parameter	Description
PGA_TCP_USER	The Oracle user ID to be used by the gateway when connecting to the Oracle database specified by the PGA_TCP_DB parameter. The user ID can be from 1 to 30 characters long. This parameter is required.
	There is no default value.
TRACE_LEVEL	PGA trace level. This controls tracing output written to STDERR (the target of the LOG_DESTINATION parameter.) The value must be an integer from 0 to 255.
	The default is 0, indicating no tracing. NOTE: This parameter will be used in the pg4tcpmap tool as well as the gateway.

B.2 Output for the pg4tcpmap Tool

The following output illustrates the results from executing the pg4tcpmap tool when running TCP/IP for IMS Connect on the gateway. Refer to Loading the PGA_TCP_IMSC TableLoading the PGA_TCP_IMSC Table of this guide and to Chapter 6 of the *Oracle Database Gateway for APPC User's Guide* for detailed information about the function and parameters of the pg4tcpmap tool.

Note that input in this sample is shown within brackets angle brackets (<>).

```
C:\oracle\bin\<pq4tcpmap>
PG4TCPMAP: Release 11.2.0.1.0 - Production on Thu Jun 11 15:09:00 2009
Copyright (c) 1982, 2009, Oracle and/or its affiliates. All rights reserved.
This tool takes the IMS Connect TCP/IP information, such as host name
and port number and maps them to your TIPs.
You may use this tool to insert or delete IMS Connect TCP/IP information.
If you want to insert a row, type I
If you want to delete a row, type D
Enter the Unique Side Profile.
IMSPGA
Enter either the remote hostname or its TCP/IP address.
Enter the IMS CONNECT port number.
Do you want to select a CONVERSATIONAL PROTOCOL? (Y|N)
The default is NO, 'no request for acknowledgment or deallocation'
Enter one of the following letters for Timer.
For .25 second, enter 'D'.
For .01 to .25 second, enter 'S'.
For 'does not set the timer, no wait occurs', enter 'N'.
For Receive waits indefinitely, enter 'I'.
The default is 'D'.
```



```
Enter one of the following letters for 'socket connection type'.
For transaction socket, enter 'T'.
For persistent socket, enter 'P'.
For non-persistent socket, enter 'N'.
The default is 'T'.
Do you want to enter the CLIENT ID name? (Y|N)
If NO, IMS CONNECT (USER EXIT) will generate it.
Enter one of the following letters for 'COMMIT MODE'.
For Commit Mode set to 0, enter '0'.
For Commit Mode set to 1, enter '1'.
The default is '1'.
Enter the DATASTORE name (IMS DESTINATION ID).
The maximum string length is 8 and the Datastore name must be specified.
Do you want to enter the LTERM? (Y|N)
If NO, the default is blank.
Do you want to enter the RACF GROUP name? (Y|N)
If NO, the default is blank.
Do you want to enter the IRM ID? (Y|N)
If NO, the default is *IRMREQ*.
Does your exit return the LLLL prefix field? (Y|N)
The default is 'N'.
Requested to INSERT a row.
'Side Profile name' is 'IMSPGA'
'remote host name' is 'MVS09'
'IMS Connect port number' is '9900'
'conversational protocol' is ' '
'Timer' is 'D'
'socket connection type' is 'T'
'client ID' is '
'commit mode' is '1'
'Datastore name (IMS destination ID)' is 'IMSE
'IMS LTERM override' is '
'RACF group name' is '
'IRM ID' is '*IRMREQ*'
'LLLL prefix present' is 'N'
PG4TCPMAP is complete.
```

B.2.1 Sample listener.ora File for a Gateway Using TCP/IP

```
LISTENER =

(ADDRESS_LIST =

(ADDRESS=

(COMMUNITY= TCP.world)

(Host = bay)

(PROTOCOL= TCP)

(Port= 2621)

)

(ADDRESS=

(COMMUNITY= TCP.world)

(Host = bay)

(PROTOCOL= TCP)
```

```
(Port= 2623)
)
)

SID_LIST_LISTENER =
(SID_LIST =
   (SID_DESC =
        (SID_NAME = PGA)
        (ORACLE_HOME = C:\oracle\pga\12.2)
        (PROGRAM = pg4t4ic)
)
)
```

B.2.2 Sample tnsnames.ora File for a Gateway Using TCP/IP



C

Gateway Terminology

The following topics contain a list of terms and definitions pertaining to the gateway and its components and function.

For a list of other terms and definitions associated with the gateway, refer to Chapter 1 of the *Oracle Database Gateway for APPC User's Guide*.

Following is a list of some of the terms and definitions used in this edition of the *Oracle Database Gateway for APPC Installation and Configuration Guide*.

Gateway Initialization File

This file is known as <code>initsid.ora</code> and it contains parameters that govern the operation of the gateway. If you are using the SNA protocol, then refer to Gateway Initialization Parameters for SNA Protocol for more information. Refer to Gateway Initialization Parameters for TCP/IP Communication Protocol if your protocol is TCP/IP.

Gateway Remote Procedure

The Oracle Database Gateway for APPC provides prebuilt remote procedures. In general, the following three remote procedures are used:

- PGAINIT, which initializes transactions
- PGAXFER, which transfers data
- PGATERM, which terminates transactions

Refer to "Remote Procedural Call Functions" in this guide and to Appendix B, "Gateway RPC Interface" in the *Oracle Database Gateway for APPC User's Guide* for more information about gateway remote procedures.

dq4pwd

 ${
m d} g 4 {
m pwd}$ is a utility which encrypts passwords that are normally stored in the gateway initialization file. Passwords are stored in an encrypted form in the password file, making the information more secure. Refer to "Passwords in the Gateway Initialization File" for detailed information about how the ${
m d} g 4 {
m pwd}$ utility works.

pg4tcpmap tool

This gateway mapping tool is applicable only when the gateway is using TCP/IP support for IMS Connect. Its function is to map the side profile name to TCP/IP and IMS Connect attributes into the PGA TCP IMSC table.

PGA

Procedural Gateway Administration (PGA) is a general reference within this guide to all or most components comprising the Oracle Database Gateway for APPC. This term is used when references to a specific product or component are too narrow.



PGDL

Procedural Gateway Definition Language (PGDL) is the collection of statements used to define transactions and data to the PGAU.

PL/SQL Stored Procedure Specification (PL/SQL package)

This is a precompiled PL/SQL procedure that is stored in Oracle database .

UTL_RAW PL/SQL Package (the UTL_RAW Functions)

This component of the gateway represents a series of data conversion functions for PL/SQL RAW variables and remote host data. The types of conversions performed depend on the language of the remote host data. Refer to "UTL_RAW Functions" in Appendix D of the *Oracle Database Gateway for APPC User's Guide* for more information.

UTL_PG PL/SQL Package (the UTL_PG Functions)

This component of the gateway represents a series of COBOL numeric data conversion functions. Refer to "NUMBER_TO_RAW and RAW_TO_NUMBER Argument Values" in Appendix D of the *Oracle Database Gateway for APPC User's Guide* for supported numeric datatype conversions.



D

Configuration Worksheet

The following worksheet lists the parameter names and the reasons you will need them to configure the gateway and the communications interface you have chosen (either SNA or TCP/IP). Use the worksheet to gather the specific information you need before you begin the configuration process.

Ask your systems administrator to provide you with any parameter names you do not know.

Table D-1 Parameters for Configuring Gateway and Communication Protocols

Name of Parameter Needed	Purpose	Your Specific Parameters Here
ORACLE_HOME	for: gateway's Oracle Home	
ORACLE_SID	for: gateway's system ID	
Any Security Options Needed	for: SNA remote LU properties options	
Suitable Name for Each Side Information Profile	for: SNA creating CPI-C symbolic destination names (side information profiles), general information	
Suitable Mode	for: SNA	
TP Name	for: SNA partner information in CPI-C name properties	
Partner LU Name Alias	for: SNA partner information in CPI-C name properties	
Unique Side Profile Name	for: Configuring TCP/IP support for IMS Connect	
Remote Host name or TCP/IP Address	for: Configuring TCP/IP support for IMS Connect, pg4tcpmap tool	
IP Address	for: Configuring TCP/IP support for IMS Connect, pg4tcpmap tool	
IMS Connect Port Number	for: Configuring TCP/IP support for IMS Connect, pg4tcpmap tool	
Conversational Protocol (Y/N)	for: Configuring TCP/IP support for IMS Connect, pg4tcpmap tool	
Timer choice: a) .25 b) .01 to .25 c) Does not exist d) Receives wait	for: Configuring TCP/IP support for IMS Connect, pg4tcpmap tool	



Table D-1 (Cont.) Parameters for Configuring Gateway and Communication Protocols

Name of Parameter Needed	Purpose	Your Specific Parameters Here
Socket Connection Type Choice:	for: Configuring TCP/IP support for IMS Connect, pg4tcpmap tool	
a) transaction		
b) persistent		
c) nonpersistent		
IMS Client ID Name	for: Configuring TCP/IP support for IMS Connect, pg4tcpmap tool	
IMS Commit Mode Choice: a) 0	for: Configuring TCP/IP support for IMS Connect, pg4tcpmap tool	
b) 1		
IMS Destination ID, datastore name	for: Configuring TCP/IP support for IMS Connect, pg4tcpmap tool	
LTERM	for: Configuring TCP/IP support for IMS Connect, pg4tcpmap tool	
RACF Group Name	for: Configuring TCP/IP support for IMS Connect, pg4tcpmap tool	
IRM_ID	for: Configuring TCP/IP support for IMS Connect, pg4tcpmap tool	
LLLL (Y/N)	for: Configuring TCP/IP support for IMS Connect, pg4tcpmap tool	



Index

Symbols	CICS Transaction Server for z/OS
	authentication mechanism
(HS=) (TNSNAMES parameter for Oracle Net),	on all platforms, 10-4
5-1	configuring for the gateway, 7-1
with TCP/IP protocol, 5-1	OLTP
	configuration verification, 8-15
A	TP name length, A-3
	command
action items	SET, 8-10, 9-12
for installing the gateway, 4-6	COMMIT, A-4
ALTER USER command, 8-3, 9-3	COMMIT_CONFIRM, A-2, A-4, B-2
american_america_us7ascii, 11-5	and PGA_CAPABILITY parameter, A-4
APPC, 1-1	capability, <i>A-4</i>
conversation security option, A-3, B-2	commit-confirm, A-4
APPC/MVS	configuring, 8-12, 8-13
configuring for the gateway, 7-1	gateway initialization parameters, 8-13
installation verification, 8-16	OLTP, 8-13
verification of configuration, 8-16	Oracle database, 8-12
architecture	sample applications, 8-17
components of the gateway, 1-5	transaction log, 8-17
ASCII	COMMIT/ROLLBACK, 3-3
automatic conversion, 1-2	communications
authentication	between server, gateway, and remote host,
for operating system, 10-2	1-6
for Oracle, 10-2	needed for Windows, 3-2
types, security, 10-2	configuration
() poo, occurry, 	gateway directories, 9-1
В	configuration verification
В	OLTP
backout possibilities during migration, 11-2	on gateway using SNA, 8-14
backout possibilities during migration, 11-2	on gateway using TCP/IP for IMS
	Connect, 9-13, 9-14
C	configuring
0100 4 0 0 0	APPC/MVS, 7-1
CICS, 1-8, 3-3	CICS Transaction Server for z/OS, 7-1
ATTACHSEC parameter, 6-1	commit-confirm, 8-12, 8-13
installation verification	gateway
on gateway using SNA, 8-15	optional steps to allow multiple users
security options not supported by the	using SNA, 8-8
gateway, 6-1	optional steps to allow multiple users
transaction ID, 8-15	using TCP/IP for IMS Connect,
verifying configuration	9-8
on gateway using SNA, 8-15	gateway directories, 8-1
	IMS/TM 7-1



configuring (continued)	dependent LU, 7-1
Oracle database, 8-12	See also LUs, 7-1
upgrading from previous releases, 8-6	describe statement
Oracle database for gateway using TCP/IP	DBMS_OUTPUT, 9-3
for IMS Connect	DESCRIBE statement
pre-configuration steps, 9-1	DBMS_OUTPUT, 8-3
TCP/IP for IMS Connect	UTL_RAW, 8-3, 9-3
on the gateway, 9-11	dfhcsdup.jcl file, 7-1
the gateway	DFHRPL DD statement, 7-1
for TCP/IP for IMS Connect, 9-1	DG4APPC
using SNA, 8-1	known restrictions, 2-1
the OLTP, 7-1	see gateway, 2-1
your network	dg4pwd utility
using SNA, 5-1	definition, C-1
configuring CICS OLTP for Transaction Server,	recommended security utility feature, on
7-1	gateway using SNA, <i>C-1</i>
· -	directories
configuring your network, 5-1	
CONNECT clause, 10-4	for installing gateway and OIS files, 8-1, 9-1
for database link security, 10-3	disk space requirements, 3-2
in TCP/IP security, 10-5	DISPLAY datatypes, 2-1
connection	
definition	E
SNA Server, 6-4	
CPI-C, 8-18	EBCDIC language, 1-2
creating profile in IBM Communications	gateway known restrictions pertaining to, 2-1
Server, 6-10	necessary to change to ASCII when using
creating	TCP/IP, 9-14
public database link, 8-3, 9-3	enhancements
public database link, 8-3, 9-3	enhancements
	enhancements using PGAU to automatically upgrade PG DD
public database link, 8-3, 9-3 D	enhancements using PGAU to automatically upgrade PG DD entries, 8-8, 9-10
<u>D</u>	enhancements using PGAU to automatically upgrade PG DD entries, 8-8, 9-10 error
D data dictionary	enhancements using PGAU to automatically upgrade PG DD entries, 8-8, 9-10 error during commit processing, A-5
D data dictionary See PG DD, 1-3	enhancements using PGAU to automatically upgrade PG DD entries, 8-8, 9-10 error during commit processing, A-5 obsolete parameters, 11-3
D data dictionary See PG DD, 1-3 data exchange	enhancements using PGAU to automatically upgrade PG DD entries, 8-8, 9-10 error during commit processing, A-5 obsolete parameters, 11-3 parameter name misspelled, 8-10, 9-12
data dictionary See PG DD, 1-3 data exchange PGAXFER function, 1-7	enhancements using PGAU to automatically upgrade PG DD entries, 8-8, 9-10 error during commit processing, A-5 obsolete parameters, 11-3 parameter name misspelled, 8-10, 9-12 treating incoming APPC CONFIRM requests
data dictionary See PG DD, 1-3 data exchange PGAXFER function, 1-7 database link, 1-6, A-5	enhancements using PGAU to automatically upgrade PG DD entries, 8-8, 9-10 error during commit processing, A-5 obsolete parameters, 11-3 parameter name misspelled, 8-10, 9-12
D data dictionary See PG DD, 1-3 data exchange PGAXFER function, 1-7 database link, 1-6, A-5 creating, 8-3, 9-3	enhancements using PGAU to automatically upgrade PG DD entries, 8-8, 9-10 error during commit processing, A-5 obsolete parameters, 11-3 parameter name misspelled, 8-10, 9-12 treating incoming APPC CONFIRM requests as errors, A-2, A-5
D data dictionary See PG DD, 1-3 data exchange PGAXFER function, 1-7 database link, 1-6, A-5 creating, 8-3, 9-3 when configuring Oracle database, 8-3,	enhancements using PGAU to automatically upgrade PG DD entries, 8-8, 9-10 error during commit processing, A-5 obsolete parameters, 11-3 parameter name misspelled, 8-10, 9-12 treating incoming APPC CONFIRM requests
data dictionary See PG DD, 1-3 data exchange PGAXFER function, 1-7 database link, 1-6, A-5 creating, 8-3, 9-3 when configuring Oracle database, 8-3, 9-3	enhancements using PGAU to automatically upgrade PG DD entries, 8-8, 9-10 error during commit processing, A-5 obsolete parameters, 11-3 parameter name misspelled, 8-10, 9-12 treating incoming APPC CONFIRM requests as errors, A-2, A-5
data dictionary See PG DD, 1-3 data exchange PGAXFER function, 1-7 database link, 1-6, A-5 creating, 8-3, 9-3 when configuring Oracle database, 8-3, 9-3 in configuring the network, 5-1	enhancements using PGAU to automatically upgrade PG DD entries, 8-8, 9-10 error during commit processing, A-5 obsolete parameters, 11-3 parameter name misspelled, 8-10, 9-12 treating incoming APPC CONFIRM requests as errors, A-2, A-5 F FDS_CLASS parameter, 11-3
data dictionary See PG DD, 1-3 data exchange PGAXFER function, 1-7 database link, 1-6, A-5 creating, 8-3, 9-3 when configuring Oracle database, 8-3, 9-3 in configuring the network, 5-1 in verifying gateway installation	enhancements using PGAU to automatically upgrade PG DD entries, 8-8, 9-10 error during commit processing, A-5 obsolete parameters, 11-3 parameter name misspelled, 8-10, 9-12 treating incoming APPC CONFIRM requests as errors, A-2, A-5 F FDS_CLASS parameter, 11-3 FDS_CLASS_VERSION
data dictionary See PG DD, 1-3 data exchange PGAXFER function, 1-7 database link, 1-6, A-5 creating, 8-3, 9-3 when configuring Oracle database, 8-3, 9-3 in configuring the network, 5-1 in verifying gateway installation on gateway using SNA, 8-14	enhancements using PGAU to automatically upgrade PG DD entries, 8-8, 9-10 error during commit processing, A-5 obsolete parameters, 11-3 parameter name misspelled, 8-10, 9-12 treating incoming APPC CONFIRM requests as errors, A-2, A-5 F FDS_CLASS parameter, 11-3 FDS_CLASS_VERSION parameter added, 11-4
data dictionary See PG DD, 1-3 data exchange PGAXFER function, 1-7 database link, 1-6, A-5 creating, 8-3, 9-3 when configuring Oracle database, 8-3, 9-3 in configuring the network, 5-1 in verifying gateway installation on gateway using SNA, 8-14 on gateway using TCP/IP for IMS	enhancements using PGAU to automatically upgrade PG DD entries, 8-8, 9-10 error during commit processing, A-5 obsolete parameters, 11-3 parameter name misspelled, 8-10, 9-12 treating incoming APPC CONFIRM requests as errors, A-2, A-5 FDS_CLASS parameter, 11-3 FDS_CLASS_VERSION parameter added, 11-4 FDS_INSTANCE parameter, 11-3
data dictionary See PG DD, 1-3 data exchange PGAXFER function, 1-7 database link, 1-6, A-5 creating, 8-3, 9-3 when configuring Oracle database, 8-3, 9-3 in configuring the network, 5-1 in verifying gateway installation on gateway using SNA, 8-14 on gateway using TCP/IP for IMS Connect, 9-13	enhancements using PGAU to automatically upgrade PG DD entries, 8-8, 9-10 error during commit processing, A-5 obsolete parameters, 11-3 parameter name misspelled, 8-10, 9-12 treating incoming APPC CONFIRM requests as errors, A-2, A-5 FDS_CLASS parameter, 11-3 FDS_CLASS_VERSION parameter added, 11-4 FDS_INSTANCE parameter, 11-3 file
data dictionary See PG DD, 1-3 data exchange PGAXFER function, 1-7 database link, 1-6, A-5 creating, 8-3, 9-3 when configuring Oracle database, 8-3, 9-3 in configuring the network, 5-1 in verifying gateway installation on gateway using SNA, 8-14 on gateway using TCP/IP for IMS Connect, 9-13 public and private, 10-2	enhancements using PGAU to automatically upgrade PG DD entries, 8-8, 9-10 error during commit processing, A-5 obsolete parameters, 11-3 parameter name misspelled, 8-10, 9-12 treating incoming APPC CONFIRM requests as errors, A-2, A-5 F FDS_CLASS parameter, 11-3 FDS_CLASS_VERSION parameter added, 11-4 FDS_INSTANCE parameter, 11-3 file dfhcsdup.jcl, 7-1
data dictionary See PG DD, 1-3 data exchange PGAXFER function, 1-7 database link, 1-6, A-5 creating, 8-3, 9-3 when configuring Oracle database, 8-3, 9-3 in configuring the network, 5-1 in verifying gateway installation on gateway using SNA, 8-14 on gateway using TCP/IP for IMS Connect, 9-13 public and private, 10-2 security, CONNECT clause, 10-3	enhancements using PGAU to automatically upgrade PG DD entries, 8-8, 9-10 error during commit processing, A-5 obsolete parameters, 11-3 parameter name misspelled, 8-10, 9-12 treating incoming APPC CONFIRM requests as errors, A-2, A-5 F FDS_CLASS parameter, 11-3 FDS_CLASS_VERSION parameter added, 11-4 FDS_INSTANCE parameter, 11-3 file dfhcsdup.jcl, 7-1 initPGA.ora, 8-10, 9-11
data dictionary See PG DD, 1-3 data exchange PGAXFER function, 1-7 database link, 1-6, A-5 creating, 8-3, 9-3 when configuring Oracle database, 8-3, 9-3 in configuring the network, 5-1 in verifying gateway installation on gateway using SNA, 8-14 on gateway using TCP/IP for IMS Connect, 9-13 public and private, 10-2 security, CONNECT clause, 10-3 database link name	enhancements using PGAU to automatically upgrade PG DD entries, 8-8, 9-10 error during commit processing, A-5 obsolete parameters, 11-3 parameter name misspelled, 8-10, 9-12 treating incoming APPC CONFIRM requests as errors, A-2, A-5 F FDS_CLASS_VERSION parameter added, 11-4 FDS_INSTANCE parameter, 11-3 file dfhcsdup.jcl, 7-1 initPGA.ora, 8-10, 9-11 initPGAI.ora, A-5
data dictionary See PG DD, 1-3 data exchange PGAXFER function, 1-7 database link, 1-6, A-5 creating, 8-3, 9-3 when configuring Oracle database, 8-3, 9-3 in configuring the network, 5-1 in verifying gateway installation on gateway using SNA, 8-14 on gateway using TCP/IP for IMS Connect, 9-13 public and private, 10-2 security, CONNECT clause, 10-3 database link name modifying .sql files, 8-14, 9-13	enhancements using PGAU to automatically upgrade PG DD entries, 8-8, 9-10 error during commit processing, A-5 obsolete parameters, 11-3 parameter name misspelled, 8-10, 9-12 treating incoming APPC CONFIRM requests as errors, A-2, A-5 F FDS_CLASS parameter, 11-3 FDS_CLASS_VERSION parameter added, 11-4 FDS_INSTANCE parameter, 11-3 file dfhcsdup.jcl, 7-1 initPGA.ora, 8-10, 9-11 initPGAI.ora, A-5 initsid.ora, 1-6, 8-10, 8-13, 9-11, 11-1, A-1,
data dictionary See PG DD, 1-3 data exchange PGAXFER function, 1-7 database link, 1-6, A-5 creating, 8-3, 9-3 when configuring Oracle database, 8-3, 9-3 in configuring the network, 5-1 in verifying gateway installation on gateway using SNA, 8-14 on gateway using TCP/IP for IMS Connect, 9-13 public and private, 10-2 security, CONNECT clause, 10-3 database link name modifying .sql files, 8-14, 9-13 datastores	enhancements using PGAU to automatically upgrade PG DD entries, 8-8, 9-10 error during commit processing, A-5 obsolete parameters, 11-3 parameter name misspelled, 8-10, 9-12 treating incoming APPC CONFIRM requests as errors, A-2, A-5 FDS_CLASS parameter, 11-3 FDS_CLASS_VERSION parameter added, 11-4 FDS_INSTANCE parameter, 11-3 file dfhcsdup.jcl, 7-1 initPGA.ora, 8-10, 9-11 initPGAI.ora, A-5 initsid.ora, 1-6, 8-10, 8-13, 9-11, 11-1, A-1, B-1, C-1
data dictionary See PG DD, 1-3 data exchange PGAXFER function, 1-7 database link, 1-6, A-5 creating, 8-3, 9-3 when configuring Oracle database, 8-3, 9-3 in configuring the network, 5-1 in verifying gateway installation on gateway using SNA, 8-14 on gateway using TCP/IP for IMS Connect, 9-13 public and private, 10-2 security, CONNECT clause, 10-3 database link name modifying .sql files, 8-14, 9-13 datastores gateway access to, 1-1	enhancements using PGAU to automatically upgrade PG DD entries, 8-8, 9-10 error during commit processing, A-5 obsolete parameters, 11-3 parameter name misspelled, 8-10, 9-12 treating incoming APPC CONFIRM requests as errors, A-2, A-5 FDS_CLASS parameter, 11-3 FDS_CLASS_VERSION parameter added, 11-4 FDS_INSTANCE parameter, 11-3 file dfhcsdup.jcl, 7-1 initPGA.ora, 8-10, 9-11 initPGAI.ora, A-5 initsid.ora, 1-6, 8-10, 8-13, 9-11, 11-1, A-1, B-1, C-1 gateway parameters for gateway using
data dictionary See PG DD, 1-3 data exchange PGAXFER function, 1-7 database link, 1-6, A-5 creating, 8-3, 9-3 when configuring Oracle database, 8-3, 9-3 in configuring the network, 5-1 in verifying gateway installation on gateway using SNA, 8-14 on gateway using TCP/IP for IMS Connect, 9-13 public and private, 10-2 security, CONNECT clause, 10-3 database link name modifying .sql files, 8-14, 9-13 datastores gateway access to, 1-1 DBMS_OUTPUT packages, 8-3, 9-3	enhancements using PGAU to automatically upgrade PG DD entries, 8-8, 9-10 error during commit processing, A-5 obsolete parameters, 11-3 parameter name misspelled, 8-10, 9-12 treating incoming APPC CONFIRM requests as errors, A-2, A-5 FDS_CLASS parameter, 11-3 FDS_CLASS_VERSION parameter added, 11-4 FDS_INSTANCE parameter, 11-3 file dfhcsdup.jcl, 7-1 initPGA.ora, 8-10, 9-11 initPGAI.ora, A-5 initsid.ora, 1-6, 8-10, 8-13, 9-11, 11-1, A-1, B-1, C-1 gateway parameters for gateway using SNA, 8-10
data dictionary See PG DD, 1-3 data exchange PGAXFER function, 1-7 database link, 1-6, A-5 creating, 8-3, 9-3 when configuring Oracle database, 8-3, 9-3 in configuring the network, 5-1 in verifying gateway installation on gateway using SNA, 8-14 on gateway using TCP/IP for IMS Connect, 9-13 public and private, 10-2 security, CONNECT clause, 10-3 database link name modifying .sql files, 8-14, 9-13 datastores gateway access to, 1-1 DBMS_OUTPUT packages, 8-3, 9-3 DBMS_PIPE, 8-3, 8-8, 9-3, 9-9	enhancements using PGAU to automatically upgrade PG DD entries, 8-8, 9-10 error during commit processing, A-5 obsolete parameters, 11-3 parameter name misspelled, 8-10, 9-12 treating incoming APPC CONFIRM requests as errors, A-2, A-5 FDS_CLASS parameter, 11-3 FDS_CLASS_VERSION parameter added, 11-4 FDS_INSTANCE parameter, 11-3 file dfhcsdup.jcl, 7-1 initPGA.ora, 8-10, 9-11 initPGAI.ora, A-5 initsid.ora, 1-6, 8-10, 8-13, 9-11, 11-1, A-1, B-1, C-1 gateway parameters for gateway using SNA, 8-10 gateway parameters for gateway using
data dictionary See PG DD, 1-3 data exchange PGAXFER function, 1-7 database link, 1-6, A-5 creating, 8-3, 9-3 when configuring Oracle database, 8-3, 9-3 in configuring the network, 5-1 in verifying gateway installation on gateway using SNA, 8-14 on gateway using TCP/IP for IMS Connect, 9-13 public and private, 10-2 security, CONNECT clause, 10-3 database link name modifying .sql files, 8-14, 9-13 datastores gateway access to, 1-1 DBMS_OUTPUT packages, 8-3, 9-3 DBMS_PIPE, 8-3, 8-8, 9-3, 9-9 definition types	enhancements using PGAU to automatically upgrade PG DD entries, 8-8, 9-10 error during commit processing, A-5 obsolete parameters, 11-3 parameter name misspelled, 8-10, 9-12 treating incoming APPC CONFIRM requests as errors, A-2, A-5 FDS_CLASS parameter, 11-3 FDS_CLASS_VERSION parameter added, 11-4 FDS_INSTANCE parameter, 11-3 file dfhcsdup.jcl, 7-1 initPGA.ora, 8-10, 9-11 initPGAI.ora, A-5 initsid.ora, 1-6, 8-10, 8-13, 9-11, 11-1, A-1, B-1, C-1 gateway parameters for gateway using SNA, 8-10
data dictionary See PG DD, 1-3 data exchange PGAXFER function, 1-7 database link, 1-6, A-5 creating, 8-3, 9-3 when configuring Oracle database, 8-3, 9-3 in configuring the network, 5-1 in verifying gateway installation on gateway using SNA, 8-14 on gateway using TCP/IP for IMS Connect, 9-13 public and private, 10-2 security, CONNECT clause, 10-3 database link name modifying .sql files, 8-14, 9-13 datastores gateway access to, 1-1 DBMS_OUTPUT packages, 8-3, 9-3 DBMS_PIPE, 8-3, 8-8, 9-3, 9-9	enhancements using PGAU to automatically upgrade PG DD entries, 8-8, 9-10 error during commit processing, A-5 obsolete parameters, 11-3 parameter name misspelled, 8-10, 9-12 treating incoming APPC CONFIRM requests as errors, A-2, A-5 FDS_CLASS parameter, 11-3 FDS_CLASS_VERSION parameter added, 11-4 FDS_INSTANCE parameter, 11-3 file dfhcsdup.jcl, 7-1 initPGA.ora, 8-10, 9-11 initPGAI.ora, A-5 initsid.ora, 1-6, 8-10, 8-13, 9-11, 11-1, A-1, B-1, C-1 gateway parameters for gateway using SNA, 8-10 gateway parameters for gateway using



file (continued)	gateway (continued)
initsid.ora (continued)	configuring (continued)
new startup shell parameters, 11-4	for TCP/IP for IMS Connect, 9-1, 9-11
parameters changed since v4, 11-3	configuring for multiple users
listener.ora, 5-1, A-5	on gateway using SNA, 8-8
oralu62.asm, 7-1	creating SNA definitions for, using SNA
oraplu62.asm, 7-1	Server Manager, 6-3
pgaccau.sql, 8-12	directory locations for configuration, 8-1, 9-2
pgacclg.asm, 8-17	factors affecting memory requirements, 3-1
pgacics.sql, 8-15	features
pgaecho.sql, <i>8-14</i> , <i>9-13</i>	application transparency, 1-2
pgaflip.asm, 7-1, 7-4	code generator, 1-2
pgaflip.jcl, 7-1	fast interface, 1-2
pgaidms.sql, 8-14	flexible interface, 1-2
pgaim.sql, <i>8-16</i> , <i>9-15</i>	location transparency, 1-2
pgaims.sql, <i>8-14</i> , <i>9-13</i> , <i>9-15</i>	Oracle database integration, 1-2
pgamvs.sql, 8-14	performs automatic conversions, 1-2
PGAU control files, 4-2	site autonomy and security, 1-2
pgddadev.sql, 8-8, 9-10	support for tools, 1-2
pgddapub.sql, <i>8-8</i> , <i>9-10</i>	functions, using SNA, 1-8
prvtpgb.plb, 8-6	initialization files, <i>C-1</i>
tnsnames.ora, 5-1, 8-3, A-5	initialization parameters
utlpg.sql, 8-7	also see PGA parameters, A-1
utlraw.sql, 8-7	described, 8-10, 9-11
FLIP transaction	for gateway using SNA, A-1
OLTP configuration	new and changed since Version 4
and verification for APPC/MVS, 8-16	gateway, 11-2
and verification for CICS Transaction	renamed since v4, 11-3
Server for z/OS, 8-15	SET, 8-10, 9-12, A-1, B-1
and verification for IMS/TM on gateway	installation
using SNA, 7-1, 8-16	first-time install, configuring the Oracle
and verification for IMS/TM on gateway	database, 8-3, 9-3
using TCP/IP, 7-4, 9-14	preinstallation procedures, 4-3
function	verification, 8-14, 9-13
put_line, 8-3, 9-3	with Oracle Universal Installer action
functions	items, 4-6
See RPC (remote procedural call), 1-6	installation steps, 4-4
See UTL_PG, C-1	installing, 4-1
see UTL_RAW, C-1	known restrictions, when using SNA, 2-1
300 012_10 111, 0 1	migrating to new release, using SNA, 11-1
	network attachment requirements, 3-1
G	overview, 1-1
astoway	parameter files, 8-10, 9-11
gateway access to IBM datastores, 1-1	also see gateway initialization
communication overview, 1-6	parameters, and PGA
	parameters, 8-10
communications with all platforms, 1-1	initPGA.ora, 8-10, 9-11
compatibility with other SNA-enabled products, 3-3	pre-installation steps for TPC/IP, 4-3
•	remote procedure, definition, <i>C-1</i>
components, 1-5, 8-1	remote transaction initiation
for SNA and TCP/IP for IMS Connect,	using SNA, 1-7
1-6	using TCP/IP, 1-7
configuring, 8-1	remote transaction termination
for multiple users, on gateway using	using SNA, 1-8
TCP/IP for IMS Connect, 9-8	using SNA, 1-8
for SNA, <u>5-1</u>	using ion in , 1-0



gateway (continued)	HS parameters (continued)
removing, 4-8	see also, (HS=), <i>11-3</i>
requirements	HS_COMMIT_STRENGTH_POINT parameter,
hardware, 3-1	11-3
restoring to previous releases, 4-3	HS_DB_DOMAIN parameter, 11-3
security options and overview, 10-1	HS_DB_INTERNAL_NAME parameter, 11-3
also see, security, 10-1	HS_DB_NAME parameter, 11-3
server	HS_DESCRIBE_CACHE_HWM parameter, 11-3
restoring previous version, 4-3	HS FDS FETCH ROWS parameter, 11-3
setting up multiple gateway instances, A-5	HS LANGUAGE parameter, 11-3
SNA security validation, 6-1, 10-3	HS_NLS_DATE_FORMAT parameter, 11-3
SNA Server function, 10-3	HS_NLS_DATE_LANGUAGE parameter, 11-3
startup shell parameters	HS_OPEN_CURSORS parameter, 11-3
FDS_CLASS_VERSION, 11-4	HS_ROWID_CACHE_SIZE parameter, 11-3
steps to install, via Oracle Universal Installer,	
4-6	1
upgrading	I
from previous release, 4-2	IBM Communications Server
preparing to upgrade, 4-2	configuring, 6-7
gateway initialization parameters	creating SNA definitions, 6-8
for commit-confirm support, 8-13	definition types, 6-8
new, <i>11-2</i>	IBM mainframe requirements, 3-3
gateway security requirements, 10-1	implementation of the gateway
gateway using TCP/IP for IMS Connect	for SNA and TCP/IP for IMS Connect, 1-6
gateway initialization parameters needed,	implied APPC, A-5
B-1	IMS Connect
transaction types, 1-8	
gpglocal, 8-3, 9-3	and security, 10-4
needed to compile PGAU-generated TIP	mainframe requirements, for gateway using TCP/IP, 3-3
specifications, 8-3, 9-3	
gpglocal package, 9-3	IMS FLIP transaction, 7-1, 7-4 IMS/TM
gpglocal.pkb script, 8-3, 9-3	
gpglocal.pkh script, 8-3, 9-3	configuring for the gateway
grant	using SNA, 7-1
access, 8-8, 9-9	installation verification
authorization, 8-3, 9-3	on gateway using SNA, 8-16
execute, 8-3, 9-3	on gateway using TCP/IP for IMS
explicit, 8-8, 9-9	Connect, 9-14
private, 8-8, 9-9	mainframe requirements for gateway using
public, 8-8, 9-9	TCP/IP, 3-3
public, 0 0, 3 3	TP name length, A-3
	verification of configuration
H	on gateway using SNA, 8-16
handuran vaninamanta 2.1	on gateway using TCP/IP for IMS
hardware requirements, <i>3-1</i>	Connect, 9-14
Heterogeneous Services (HS), 11-3	independent LU, 7-1
and Oracle Net considerations, on gateway	initialization files
using SNA, 11-2	See gateway initialization files, also see PGA
catalogs	parameters, <i>C-1</i>
installing, on gateway using SNA, 8-3	initiating remote transactions, 1-7
installing, on gateway using TCP/IP for	initPGA.ora file, 8-10, 9-11
IMS Connect, 9-3	initPGAI.ora file, A-5
parameters needed for gateway using	initsid.ora file, 1-6, 8-10, 8-13, 9-11, 11-1, A-1,
TCP/IP, 11-2	B-1, C-1
HS parameters, 11-3	gateway parameters on gateway using SNA,
description, 11-1, 11-2	8-10



initsia.ora file (continuea)	LUS, 6-1
gateway parameters on gateway using	also see independent LU and dependent LU,
TCP/IP for IMS Connect, 9-11	6-1
HS parameter descriptions, 11-1, 11-2	and gateway security, 10-3
new parameters, on gateway using SNA,	dependent
11-3	for configuring LU6.2 for IMS/TM for the
new startup shell parameters, 11-4	gateway, 7-1
parameters changed since v4, 11-3	in SNA security validation, 10-3
installation	independent
steps, 4-4	in configuring APPC/MVS on the
installation verification	gateway, 7-1
CICS on gateway using SNA, 8-15	in configuring CICS Transaction Server
	for z/OS, 7-1
gateway	
with SNA, 8-14	in configuring IMS/TM for the gateway,
with TCP/IP for IMS Connect, 9-13	7-1
IMS/TM	vs. dependent, 6-2
on gateway using SNA, 8-16	
on gateway using TCP/IP for IMS	M
Connect, 9-14	
OLTP, 8-15	mainframe requirements, 3-3
installing	memory requirements, 3-1
and configuring the gateway, 4-1	Microsoft Host Integration Server
preinstallation steps, 4-3	and LUs, 6-2
sample applications	configuring, 6-2
on gateway for SNA protocol, 8-18	creating SNA definitions on, 6-4
on gateway with TCP/IP for IMS	See SNA Server, 3-2
Connect, 9-15	
IPC	Microsoft Windows
	configuring the SNA Server, 6-1
key, 5-1	migrating
protocol, 5-1	an existing gateway to use TCP/IP, 11-5
	backout considerations when migrating to
K	new release, 11-2
	existing gateway instance to new release,
key	using SNA, <i>11-1</i>
IPC, 5-1	to 12.2.0.1.0
known restrictions	special parameters, 11-2
for DG4APPC, 2-1	mode definition, 6-5
for PGAU, 2-2	multiconversational transaction type, for gateway
	using TCP/IP, 1-8
L	
that a smaller deflection of 4	N
link service definition, 6-4	
listener.ora file, 5-1, A-5	network
sample file for gateway using SNA, A-6	configuring
sample for gateway using TCP/IP, B-4	with SNA, 5-1
LOG_DESTINATION parameter, 11-3	reconfiguring, 5-1
for gateway using SNA, 11-2	networking products required, 3-2
for gateway using TCP/IP, B-2	non-persistent socket transaction type for TCP/IP
logmode entry name, 8-15	for IMS Connect, 1-8
LU6.1 Adapter for LU6.2 applications, 7-1	•
LU6.2	
and specifying SNA conversation security,	0
10-3	sheelete management in material 2011 44 0
10-3	obsolete parameters, in gateway using SNA, 11-3



OLTP, 6-6, A-4	Oracle database (continued)
and dependent LUs, 6-2	and TCP/IP for IMS Connect
and SECURITY=PROGRAM option, 10-4	pre-configuration steps, 9-1
and SECURITY=PROGRAM option, on	component of the gateway, 1-5
platforms using TCP/IP, 10-5	configuring for commit-confirm, 8-12
configuration, 7-1	definition, 1-3
configuration verification	enabling DBMS_OUTPUT PL/SQL package
APPC/MVS, 8-16	8-3, 9-3
CICS Transaction Server for z/OS, 8-15	logon authentication needed, 10-2
on gateway using SNA, <i>8-14</i>	multiple servers on the gateway
on gateway using SNA IMS/TM, 8-16	using TPC/IP, 1-5
on gateway using TCP/IP for IMS	multiple servers on the gateway using SNA,
Connect, 9-13	1-5
configuring	precompiles PL/SQL package, 1-2
	READ_ONLY mode, A-4
APPC/MVS for the gateway, 7-1 CICS Transaction Server for z/OS for the	role
gateway, 7-1	in gateway communication, 1-6
for gateway using TCP/IP for IMS	in logon security, 10-3
Connect, 9-11	in starting the gateway, 1-6
IMS/TM for the gateway, 7-1	shipped with PL/SQL packages, 8-8, 9-9
currently supported types, 7-1, 8-15	stores PL/SQL, C-1
definition, 1-3	upgrading
for TCP/IP for IMS Connect, 1-5	from previous releases, 8-6
in gateway architecture featuring SNA, 1-5	verifying
in gateway using TCP/IP, 1-5	APPC/MVS configuration, 8-16
installation verification, 8-15, 9-14	gateway installation with SNA, 8-14
post-installation steps	gateway installation with TCP/IP for IMS
on gateway using TCP/IP for IMS	Connect, 9-13
Connect, 9-15	IMS/TM, on gateway using SNA, 8-16
postinstallation steps	IMS/TM, on gateway using TCP/IP for
on gateway using SNA, 8-18	IMS Connect, 9-15
remote, 1-1	version requirements, 3-2
requirements, 3-3	Oracle Database 10g Server
security and inbound APPC session	and networking products needed, 3-2
requests, 6-1	Oracle Database Gateway for APPC
security on the gateway, 10-1	development environment, 1-2
SNA security option	functions, 1-8
on all platforms, 10-4	removing, 4-8
user ID mapping, 10-3	see also gateway, 1-8
verifying configuration	Oracle Database Listener, 5-1
on gateway using SNA, 8-15	Oracle global transaction ID, 8-17
on gateway using TCP/IP for IMS	Oracle Heterogeneous Services
Connect, 9-14	See Heterogeneous Services, 11-3
OLTP for SNA	Oracle Net, 1-3, A-2
mainframe requirements, 3-3	considerations, when migrating gateway
OLTP for TCP/IP	featuring SNA, 11-2
IBM mainframe requirements, 3-3	Heterogeneous services/tnsnames.ora
one-shot transaction types, for gateway using	considerations, on gateway using
SNA, 1-8	SNA, 11-2
online transaction processor	on gateway using TCP/IP, <i>B-2</i>
See OLTP, 1-5	security considerations, 10-2
Oracle database, 1-7, 4-1, 4-3, 4-4, 5-1, 8-3, 9-3,	to start the gateway, 1-6
10-2, A-4, A-5	Oracle Net Listener, 5-1
and gateway security, 10-3	

Oracle Universal Installer	persistent transaction type, for gateway using
using, 4-6	SNA, <i>1-8</i>
to install gateway, 4-6	PG Data Dictionary
ORACLE_HOME, 7-1, 8-10, 8-16, 9-11	See PG DD, 1-3
oralu62.asm file, 7-1	PG DD
ORAPGA.APPCMVS.SAMPLIB, 7-1	after upgrade, 4-2
oraplu62.asm file, 7-1	allowing multiple users, 8-8, 9-8
override	creating public synonyms for multiple users,
user ID and password, 10-4, 10-5	8-8, 9-8
·	definition, 1-3
P	install script, 8-3, 9-3
Ρ	installing for gateway configuration, 8-3, 9-3
package	no access from earlier PGAU versions, 4-2
DBMS_OUTPUT, 8-3, 9-3	restoring previous version, 4-3
gpglocal, 9-3	tables, 8-8, 9-9
UTL PG, 8-3, 9-3, 9-9	upgrade when upgrading gateway, 8-7
invalidated or removed, 8-7	using PGAU to upgrade existing entries, 8-8
UTL RAW, 8-3, 9-3	9-10
invalidated or removed, 8-7	pg4tcpmap table, <u>11-5</u>
package specifications	see PGA_TCP_IMSC table, 9-12
avoid reinstalling, 8-7	pg4tcpmap tool, 9-12, 10-4, 10-5, 11-5, B-2, B-3
	definition, <i>C-1</i>
reinstalling, 8-7 parameter files	function, 1-2, 9-12
•	in remote transaction initiation, 1-7
See gateway initialization files, <i>A-1</i> , <i>B-1</i>	on gateway using TCP/IP, 9-3, B-2
See PGA parameters, A-1, B-1	output sample, B-3
See RRM parameters, A-1, B-1	PGA
parameters	definition, <i>C-1</i>
changed since Release 4, on gateway using	initialization files
SNA or TCP/IP, 11-2	initPGAI.ora and initPGAU.ora, A-5
FDS_CLASS_VERSION, 11-4	PGA parameters
gateway initialization parameter, described,	described, 8-10, 9-12
8-10, 9-11	list of, for gateway using TCP/IP, <i>B-2</i>
needed for commit-confirm support, 8-13	LOG_DESTINATION, A-1
new	on gateway using
FDS_CLASS (startup shell), 11-3	SNA, <i>A-1</i>
FDS_INSTANCE (startup shell), 11-3	TCP/IP, <i>B-1</i>
obsolete, in gateway using SNA, 11-3	PGA_CAPABILITY, 8-10, 9-12, A-2, B-2
PGA	choosing settings, A-3
described for SNA, 8-10	options for updating foreign databases,
described for TCP/IP, 9-12	A-4
renamed since version 4 (gateway	protections against data problems, A-4
initialization), 11-3	PGA_CAPABILITY, for gateway using
see PGA parameters and gateway, 9-11	TCP/IP, B-2
USING, 5-1	PGA_CONFIRM, A-2
password	choosing settings, A-5
change using ALTER USER command, 8-3,	PGA_LOG_DB, A-2, B-2
9-3	PGA_LOG_DB, A-2, B-2 PGA_LOG_PASS, A-2, B-2
Oracle authentication, 10-2	
Oracle password to be used by gateway, A-2	on gateway using TCP/IP, <i>B-2</i> PGA_LOG_USER, <i>A-2</i> , <i>B-3</i>
using TCP/IP, <i>B-2</i>	PGA_LOG_USER, A-2, B-3 PGA_RECOVERY_PASS, A-3
overrides, 10-4, 10-5	
with operating system authentication, 10-2	PGA_RECOVERY_TPNAME, A-3
PDS (partitioned dataset), 7-1	PGA_RECOVERY_USER, A-3
persistent socket transaction type	PGA_SECURITY_TYPE, 10-3-10-5, A-3,
for TCP/IP for IMS Connect, 1-8	B-2

PGA parameters (continued)	PGAU, 5-1
PGA TCP PASS	-generated TIP specifications, 1-6
for gateway using TCP/IP, <i>B-2</i>	-generated TIP specifications use UTL PG,
TRACE_LEVEL, A-3	8-3, 9-3
on gateway using TCP/IP, B-3	-generated TIP specifications use UTL_RAW,
PGA CAPABILITY	8-3, 9-3
See PGA parameters, A-3	accesses definitions in PG DD, 1-3
PGA CONFIRM	control files, 4-2
See PGA parameters for gateway using SNA	definition
or TCP/IP, A-5	
	used to generate TIP specifications, 1-3
PGA_SECURITY_TYPE	known restrictions in this release, 2-2
See PGA parameters, 10-3, 10-5	purpose of PGDL, <i>C-1</i>
PGA_SECURITY_TYPE parameter	restoring previous versions, 4-3
and TCP/IP security, 10-5	setting up, A-5
PGA_TCP_DB	upgrading existing PG DD entries, 8-8, 9-10
PGA parameter	PGAU commands
for gateway using TCP/IP, B-2	DEFINE DATA
PGA_TCP_DB parameter (TCP/IP only), 11-3	COBOL COPY REPLACE restrictions,
PGA_TCP_DB PGA parameter (TCP/IP only),	2-2
B-2	GENERATE, 8-8, 9-10
PGA_TCP_IMSC table, 11-5	produces TIP in output files, 8-8, 9-11
for mapping SNA parameters to TCP/IP, 9-12	to upgrade existing TIPs, 8-8, 9-10
loading, on gateway using TCP/IP, 9-12	PGAXFER function, 1-7, C-1
PGA_TCP_PASS parameter (TCP/IP only), 11-3	PGDD
PGA_TCP_PASS PGA parameter (TCP/IP only),	compatibility issues between new and older
B-2	gateways, 8-8
PGA_TCP_USER parameter (TCP/IP only), 11-3,	pgddadev.sql
B-3	file, 8-8, 9-10
PGAADMIN, 8-3, 8-14, 9-3, 9-13	script, 8-8, 9-10
creating the gateway administrator user ID,	pgddapub.sql
8-3, 9-3	file, <i>8-8</i> , <i>9-10</i>
,	
granting access to additional users, 8-8, 9-8	script, 8-8, 9-10
granting execution privileges on	pgddcr8.sql script, 8-3, 9-3
DBMS_PIPE, <i>8-3</i> , <i>9-3</i>	pgddcr8r.sql script, 8-8
initial password during creation, 8-3, 9-3	PGDDDEF role, 8-8, 9-9
pgaccau.sql file, 8-12	PGDDGEN role, 8-8, 9-9
pgacclg.asm file, 8-17	adding a privilege for upgrading PG DD
pgacics.sql file, 8-15	entries, 8-8, 9-10
pgacr8au.sql script, 8-3, 9-3	pgddupgr.sql script, 8-7
pgaecho.sql file, 8-14, 9-13	PGDL (Procedural Gateway Definition Language)
pgaflip.asm file, 7-1, 7-4	definition, C-1
pgaflip.jcl file, 7-1	PL/SQL, 1-3
PGAI	code generator, <i>1-2</i>
setting up, A-5	datatypes
pgaidms.sql file, 8-14	converted to RAW, 1-7
pgaims.sql, 9-1	function in the gateway, 1-1, 1-6
pgaims.sql file, 8-14, 8-16, 9-13	running pgatiptr.sql script to create routines,
on gateway using TCP/IP, 9-15	8-3, 9-3
pgaimsc.sql, 9-3	UTL_PG package function, <i>C-1</i>
PGAINIT, 1-7	UTL RAW function, C-1
PGAINIT function, 1-7, C-1	UTL_RAW package installation
PGAINIT TIP, 9-12	on gateway using SNA, 8-3
pgamvs.sql file, 8-14	on gateway using TCP/IP for IMS
	- · · · · · · · · · · · · · · · · · · ·
PGATERM function, 1-7, C-1	Connect, 9-3
pgatiptr.sql script, 9-3	

PL/SQL package	remote transaction initiation (continued)
definition, 1-3, C-1	on gateway using TC/IP, 1-7
developer access to, 8-8, 9-9	remote transaction program
enabled, 8-3, 9-3	See RTP, <i>1-1</i>
functions, 1-6	remote transaction termination
See TIP, 1-6	on gateway using SNA, 1-8
PL/SQL stored procedure, 8-12	on gateway using TCP/IP for IMS Connect,
used for logging transactions, 8-12	1-8
PL/SQL stored procedure specification	removing
also called "TIP", 1-2	the gateway, 4-8
See PL/SQL package, C-1	requirements
post-installation steps for OLTP	hardware, 3-1
on gateway using TCP/IP, 9-15	network attachments, 3-1
postinstallation steps for OLTP	software, 3-2
on gateway using SNA, 8-18	system, 3-1
preinstallation steps	restoring a previous release of the gateway, 4-3
for SNA, 4-3	restrictions
privileges	on gateway using SNA, 2-1
needed to create TIPs, 8-8, 9-10	role
Procedural Gateway Administration	PGDDDEF, 8-8, 9-9
See PGA, <i>C-1</i>	PGDDGEN, 8-8, 9-9
Procedural Gateway Administration Utility	ROLLBACK, 3-3, A-4
See PGAU, 1-6	RPC
processor OLTP	definition, 1-3
configuring, for commit-confirm, 8-13	function
processor requirements, 3-1	
·	PGAINIT, <i>1-7, C-1</i> PGATERM, <i>C-1</i>
protocol IDC 5-1	
IPC, 5-1	PGAXFER, 1-7, C-1
TCP, <i>5-1</i>	within the gateway, 1-1, 1-6
prvtpgb.plb	processing, 1-1
file, 8-6	RTP
script, 8-3, 8-6	definition, 1-3
prvtrawb.plb script, 8-3, 8-6, 9-3	executing, 1-3
public synonyms for multiple PG DD users, 8-8,	function in the gateway, 1-1
9-8	PGA_CAPABILITY settings for read-only
put_line function, 8-3, 9-3	RTPs, <i>A-3</i>
_	
R	S
RACF, 10-5, B-2	sample applications
READ ONLY	included, 8-18, 9-15
PGA_COMPATIBILITY setting, A-3	installing, 8-18, 9-15
recompiling TIPs	script
See TIP, 8-7	gpglocal.pkb, 8-3, 9-3
reinstallation of package specifications, 8-7	gpglocal.pkb, 8-3, 9-3
release-specific information	pgacr8au.sql, 8-3, 9-3
restrictions, 2-1	pgddadev.sql, 8-8, 9-10
	pgddapub.sql, 8-8, 9-10
remote host transactions (RHT)	pgddcr8.sql, 8-3, 9-3
types, 1-8	pgddcr8r.sql, 8-8
remote procedural call	
See RPC, 1-1	pgddupgr.sql, 8-7
remote procedure	prvtpgb.plb, 8-3, 8-6
definition, <i>C-1</i>	prvtrawb.plb, 8-3, 8-6, 9-3 utlpg.sql, 9-3
remote transaction initiation	
on gateway using SNA, 1-7	utlraw.sql, 8-3, 9-3



security	SNA security options
and database links, 10-2	SECURITY=NONE, 10-3
and SNA validation, 10-3	SECURITY=PROGRAM, 10-4
authenticating application logons, 10-2	SNA Server
authentication mechanisms	and SNA security validation, 10-3
in SNA security, 10-4	configuring an IBM Communications Server,
for TCP/IP for IMS Connect, 10-4	6-7
link accessibility for public and private	configuring on Windows, 6-1
databases, 10-2	connection definition, 6-4
links and CONNECT clauses, 10-3	CPI-C symbolic destination names, 6-6
overview of gateway security requirements,	definition types, 6-3
10-1	dependent LUs, 6-2
processing inbound connections, 6-1	function in gateway communication, 10-3
specifying SNA conversation security, 10-3	independent LUs, 6-2
security validation, 10-3	link service definition, 6-4
SECURITY=NONE SNA security option, 10-3	mode definition, 6-5
SECURITY=NONE TCP/IP security option, 10-5	remote LU definition, 6-6
SET	required for Microsoft Windows, 3-2
gateway initialization parameter, 8-10, 9-12	SNA Server definition
SET command, 8-10, 9-12	creating, using MS Host Integration Server,
shells	6-4
see Bourne, Korn, and C shells, 4-1	SNA Server Manager, 6-4
Side Information	creating SNA definitions, using MS Host
aka CPI-C symbolic destination names, 6-6	Integration Server, 6-4
side profile name, 8-15	using, to create SNA definitions for the
SINGLE SITE	gateway, 6-3
and PGA_CAPABILITY parameter, A-4	SNA Server selection, 6-4
SNA	SNACFG command, 6-3
and gateway components, 1-5	snacfg.ctl file
implementation of the gateway, 1-6	sample server definitions, 6-3
migrating existing gateway to the new	socket file descriptor
release, <i>11-1</i>	returned by TCP/IP network to PGAINIT, 1-7
new gateway initialization parameters, 11-2	software requirements, 3-2
parameters, 1-7	SQL*Plus
PGA parameters, A-1	sample, used when gateway and Oracle
preinstallation procedures, 4-3	database share computer, 8-3
remote transaction initiation, 1-7	sample, used when gateway and Oracle
remote transaction termination on the	database share machine, 9-3
gateway, 1-8	to configure Oracle database, 8-3, 9-3
security validation, 6-1, 10-3	use in configuring Oracle database for
transaction types, 1-8	Commit-Confirm, 8-12
using SNA Node Configuration menu, 6-8	using to connect to Oracle database, 8-3, 9-3
SNA APPC	statement
function in the gateway, 1-1	describe, 9-3
see also APPC, 1-1	DESCRIBE, 8-3
SNA communication package, 8-15, 8-16	DFHRPL DD, 7-1
configuration for the gateway, 5-1	system identifier
SNA definitions	choosing, 4-3
See SNA Server definitions, 6-3	system requirements, 3-1
SNA Node Configuration	3, 33
using, to configure IBM Communications	т
Server, 6-8	Т
SNA profiles, 10-3	TCP protocol, 5-1
SNA protocol	TCP/IP
gateway initialization parameters, <i>A-1</i>	specifying conversation security, 10-5
3	specifying conversation security, 10-3

TCP/IP for IMS Connect	TIP (continued)
and Remote Transaction Initiation, 1-7	body output files, 8-8, 9-11
configuring	conversions, 1-2
for the gateway, 9-11	converting PL/SQL datatypes to RAW, 1-7
gateway to permit multiple users, 9-8	definition, 1-3
function in the gateway, 1-1	developer access to PL/SQL packages, 8-8,
gateway initialization parameters, list, B-1	9-9
gateway preinstallation procedures, 4-3	developer authorization on gpglocal, 8-3, 9-3
gateway support for, description, 1-2	functions, 1-6
Heterogeneous Services parameters	in Oracle database, 1-7
needed, <i>11-2</i>	invalidated if package specifications
HS parameter descriptions, 11-1, 11-2	reinstalled, 8-7
implementation of the gateway, 1-6	override, 10-4
IMS Connect release required on IBM	override, in security for TCP/IP, 10-5
mainframe, 3-3	recompile
installing sample applications, 9-15	after reinstalling package specifications,
loading the PGA_TCP_IMSC table, 9-12	8-7
mapping SNA parameters to, 9-12	on upgrade from release 4.0.1, 4-2
migrating existing gateway using SNA to	recompile upon upgrade from SNA to
TCP/IP, 11-5	TCP/IP, 4-2, 9-14
necessary to recompile TIPs when changing	recompiling when changing from SNA to
communication protocol, 9-14	TCP/IP, 9-14
new gateway initialization parameters, 11-2	regenerate to upgrade function and
non-persistent socket transaction type, 1-8	maintenance, 8-8, 9-10
OLTP in gateway architecture, 1-5	remote transaction initiation (PGAINIT), 1-7
parameter files	specification output files, 8-8, 9-11
also see gateway initialization	specifications, 8-3, 8-8, 9-3, 9-9, 9-10
parameters, and PGA	generated by PGAU, 1-6
parameters, 9-11	use UTL_PG, 8-3, 9-3
performing post-installation procedures, 9-15	use UTL_RAW, 8-3, 9-3
persistent socket transaction type, 1-8	specifying LUs, 6-2
pg4tcpmap tool output sample, <i>B-3</i>	trace access PL/SQL routines, 8-3
PGA parameters, 9-12, B-1	upgrade considerations from previous
PGA_TCP_DB parameter, <i>B-2</i>	versions, 4-2
PGA_TCP_USER parameter, <i>B-3</i>	tnsnames.ora file, 5-1, 8-3, A-5
remote transaction initiation, 1-7	and Oracle Net considerations, 11-2
remote transaction termination, 1-8	sample file for gateway using SNA, A-6
security, 10-4	sample for gateway using TCP/IP, <i>B-5</i>
security options SECURITY=NONE, 10-5	TP name, A-3 trace access, 8-3
SECURITY=NONE, 10-3 SECURITY=NONE, on all platforms,	TRACE LEVEL parameter, 11-3, A-3
10-5	on gateway using SNA, A-3
SECURITY=PROGRAM, 10-5	on gateway using TCP/IP for IMS Connect,
TIP recompile needed on upgrade, 4-2, 9-14	B-3
TRACE_LEVEL parameter, <i>B-3</i>	Transaction Interface Package
transaction types, 1-8	See TIP, 1-3
using pg4tcpmap tool, <i>B-2</i>	transaction socket
verifying	transaction type for TCP/IP, 1-8
gateway installation, 9-13	transaction types
OLTP configuration, 9-14, 9-15	for TCP/IP for IMS/Connect, 1-8
TCP/IP protocol adapter	one-shot, persistent and multi-
for SNA, 5-1	conversational, for SNA, 1-8
terms, gateway terms defined, 1-3	transferring
TIP	initsid.ora gateway initialization file
Also called PL/SQL package, 1-6	parameters, <u>11-1</u>
- · · · · · · · · · · · · · · · · · · ·	· · · · · · · · · · · · · · · · · · ·

transparency	UTL_RAW (continued)	
(application), 1-2	PL/SQL package (continued)	
(location), on gateway using SNA, 1-2	utlpg.sql	
	file, 8-7	
U	script, 9-3	
O	utlraw.sql	
upgrading	file, 8-7	
considerations, 4-2	script, 8-3, 9-3	
existing TIP specifications, 8-8, 9-10		
user ID	V	
as security authentication, 10-2	<u> </u>	
user ID mapping	VTAM, 7-1	
OLTP, 10-3	configuring for connection to the gateway,	
USING parameter, 5-1	7-1	
utility	VTAM logmode table, 7-1	
dg4pwd, <i>C-1</i>		
UTL_PG, 8-8, 9-9	W	
installing, 8-3, 9-3	V V	
package, 9-9	Windows	
definition, C-1	and security, 10-3	
invalidated or removed, 8-7	communication protocol needed, 3-2	
UTL_RAW, 8-3, 8-8, 9-3, 9-9	configuring SNA, 5-1	
interface	operating system, 1-5	
PL/SQL package, 9-9	processing inbound connections, 6-1	
package	SNA conversation security, 10-3	
invalidated or removed, 8-7	•	
PL/SQL package	Z	
definition, C-1	<u></u>	
	z/OS, 1-2, 1-3, 3-3, 7-1	

