

Configuring Weblogic Server 14c
Oracle Banking Enterprise Limits and Collateral
Management
Release 14.7.2.0.0

Part Number: F98472-01

December 2023



Table of Contents

1. Introduction	1
1.1 Purpose of this Document.....	1
1.2 WebLogic Server Overview	1
1.3 Pre-requisites	4
2. Domain Configuration	6
2.1 Domain Creation	6
2.2 Pack and Unpack Domain	16
2.3 Start Admin server	16
2.4 Start Node Manager.....	16
3. Cluster Configuration	17
3.1 Machines Configuration	17
3.2 Dynamic Cluster Creation	20
3.3 Managed Server Template configuration.....	24
3.4 Quartz Properties	27
4. Tuning	28
4.1 General Parameters.....	28
4.2 JVM Tuning.....	28
5. Start Managed Servers	30
Starting using scripts.....	30
Starting using console.....	30
6.1 Data source creation: non XA.....	31
6.2 XA Datasource	35
6.3 JDBC Parameters Tuning	39
7. JMS Resource Creation.....	40
8. Oracle WebLogic Load Balancing	41
9. Frequently Asked Questions	42
9.1 Machine status is Unreachable.....	42
9.2 How to restart node manager?	42
9.3 Scaling Up Dynamic Cluster	42
9.4 Session Timeout	44

1.Introduction

1.1 Purpose of this Document

The purpose of this document is to explain the steps required for Configuration and applying best practices in cluster mode for

- ELCM 14.7
- Weblogic Version 14.1.1.0.0
- JDK 1.8.0_341

1.2 WebLogic Server Overview


This section of the document provides brief explanation on the main components involved in WebLogic server.

Domain


A domain is the basic administration unit for WebLogic Server instances. A domain consists of one or more WebLogic Server instances (and their associated resources) that is managed with a single Administration Server. Multiple domains can be defined based on different system administrators' responsibilities, application boundaries, or geographical locations of servers. Conversely, a single domain can be used to centralize all WebLogic Server administration activities.

Each WebLogic Server domain must have one server instance that acts as the Administration Server. Administration Server can be used via the Administration Console or using the command line for configuring all other server instances and resources in the domain.

WebLogic Domain Structure



Weblogic 14c Domain Overview



Administration Server

A domain includes one WebLogic Server instance that is configured as an Administration Server.

All changes to configuration and deployment of applications are done through the Administration Server. The Administration Server provides a central point for managing the domain and providing access to the WebLogic Server administration tools.

These tools include the following:

- WebLogic Server Administration Console: Graphical user interface to the Administration Server.
- WebLogic Server Node Manager: A Java program that lets you start and stop server instances - both Administration Servers and Managed Servers - remotely, and to monitor and automatically restart them after an unexpected failure.

Admin server start mode needs to be configured as Production Mode.

Managed Server

In a domain, server instances other than the Administration Server are referred to as Managed Servers. Managed servers host the components and associated resources that constitute your applications—for example, JSPs and EJBs.

When a Managed Server starts up, it connects to the domain's Administration Server to obtain configuration and deployment settings. In a domain with only a single WebLogic Server instance, that single server works as both the administration server and managed server.

Node Manager

The Managed Servers in a production WebLogic Server environment are often distributed across multiple machines and geographic locations.

Node Manager is a Java utility that runs as separate process from WebLogic Server and allows you to perform common operations tasks for a Managed Server, regardless of its location with respect to its Administration Server. While use of Node Manager is optional, it provides valuable benefits if your WebLogic Server environment hosts applications with high availability requirements.

If you run Node Manager on a machine that hosts Managed Servers, you can start and stop the Managed Servers remotely using the Administration Console or from the command line. Node Manager can also automatically restart a Managed Server after an unexpected failure.

Machine

A machine in the Weblogic Serve context is the logical representation of the computer that hosts one or more Weblogic Server instances(servers). The Admin Server uses the machine definitions to start remote servers through the Node Managers that run on those servers. A machine could be a physical or virtual server that hosts an Admin or Managed Server that belongs to a domain.

Managed Server Cluster

Two or more Managed Servers can be configured as a WebLogic Server cluster to increase application scalability and availability. In a WebLogic Server cluster, most resources and services are deployed to each Managed Server (as opposed to a single Managed Server,) enabling failover and load balancing.

The servers within a cluster can either run on the same machine or reside in different machines. To the client, a cluster appears as a single WebLogic Server instance.

Dynamic Cluster

A dynamic cluster is any cluster that contains one or more dynamic servers. Each server in the cluster will be based upon a single shared server template. The server template allows you to configure each server the same and ensures that servers do not need to be manually configured before being added to the cluster. This allows you to easily scale up or down the number of servers in your cluster without the need for setting up each server manually. Changes made to the server template are rolled out to all servers that use that template.

You cannot configure dynamic servers individually; there are no server instance definitions in the config.xml file when using a dynamic cluster. Therefore, you cannot override the server template with server-specific attributes or target applications to an individual dynamic server instance.

When configuring your cluster you specify the maximum number of servers you expect to need at peak times. The specified number of server instances is then created, each based upon your server template. You can then start up however many you need and scale up or down over time according to your needs. If you need additional server instances on top of the number you originally specified, you can increase the maximum number of servers instances (dynamic) in the dynamic cluster configuration.


Server Templates

A single server template provides the basis for the creation of the dynamic servers. Using this single template provides the possibility of every member being created with exactly the same attributes. Where some of the server-specific attributes like Servername, listen-ports, machines, etc. can be calculated based upon tokens.

You can pre-create server templates and let Weblogic clone one when a Dynamic Cluster is created.

When none is available a server template is created with the Dynamic Cluster. The name and the listen ports are the only server template attributes that you provide during Dynamic Cluster creation.

Simplified Configuration with Scalability and Elasticity



1.3 Pre-requisites

In this document, we are going to create a domain with two managed servers. The managed servers are going to be created on two different physical servers (nodes). Note that, this document has been prepared based on a test conducted in Linux servers.

This requires Weblogic Server of same version to be installed on both the machines and services.

Environment

2 servers where linux is installed, 1 will be primary where admin console will be running along with managed servers and the other where only managed servers will be.

Softwares

- 1) Oracle Weblogic Server 14.1.1.0.0 installed on both the machines under same folder structure.
- 2) JDK 1.8 Latest available version installed on both the machines. In this document JDK1.8.0_341 version is used.

Clock Synchronization

The clocks of both the servers participating in the cluster must be synchronized to within one second difference to enable proper functioning of jobs otherwise it will lead to session timeouts.

Enable Graphical User Interface (GUI)

Establish a telnet or SSH connection to primary server. Start X-manager (or any similar tool) in windows desktop. Export DISPLAY environment variable to the machine IP where x-manager is running.

Syntax: `export DISPLAY=<ip-address>:<port>`

Test using `xclock`

2. Domain Configuration

2.1 Domain Creation


Weblogic domain creation and configuration will be done from primary server.

From primary server, launch the fusion Middleware configuration wizard using the command **config.sh** available under \$WLS_HOME/common/bin directory.

- 1) In the Welcome screen, select **Create a new domain** option. Enter the domain name and click on **Next**.



- 2) Select the required templates from **Available Templates** and click **Next**.



3) Specify Administrator **User Name** and **Password**.

- The specified credentials are used to access Administration console.
- You can use this screen to define the default WebLogic Administrator account for the domain. This account is used to boot and connect to the domain's Administration Server. Click **Next**.

Administrator Account

ORACLE
FUSION MIDDLEWARE


Create Domain
Templates
Administrator Account
Domain Mode and JDK
Advanced Configuration
Configuration Summary
Configuration Progress
End Of Configuration

Name: weblogic
Password:
Confirm Password:


Must be the same as the password. Password must contain at least 8 alphanumeric characters with at least one number or special character.

Help < Back **Next >** Finish Cancel


- 4) Select Server Startup as **Production Mode** and the available **JDKs**. Click **Next**.



5) Select the check box adjacent to **Administration Server** and **Node Manager**. Click **Next**.



6) Specify the **Administration Server Listen address** and **Listen port**.




Note: The default Listen port is 7001 and SSL port is 7101. This could be changed to any other available port. Ensure to make a note, of this port since the same is required for launching the Admin console, post domain creation.

Note: Check for the port availability using the command - `netstat -anp |grep <Port no>`

The next screen displays **Node Manager Configuration**.

7) Configure **Node Manager**.

Select **Per Domain Default Location** option from **Node Manager Type**. And in the **Node Manager Credentials**, provide the username and password of the node manager. Click **Next**.



- 8) Verify the details and click **Create**. The domain creation process is initiated and the progress of completion is indicated.

Configuration Summary

ORACLE
FUSION MIDDLEWARE

View: Deployment

FCUBSDomain (/scratch/app/w12c/user_projects/)

- Server
 - AdminServer

Name	Basic WebLogic Server Domain
Description	Create a basic WebLogic Server domain
Author	Oracle Corporation
Location	/scratch/app/w12c/wserver/commo

Select **Create** to accept the above options and start creating and configuring a new domain. To change the above configuration before starting Domain Creation, go back to the relevant page by selecting its name in the left pane, or by using the **Back** button.

Help < Back Next > **Create** Cancel

9) Click **Next**.



10) The **Configuration Success** message will be displayed as follows:



The Admin Server console URL is as indicated below:

http://<IP address>:<admin console port>/console

- 1) <IP address >: Host on which domain was created.
- 2) <admin console port> : Port specified in Administration Server configuration page.

In this case the Admin Console URL is: <https://<server1hostname>:7101/console>

2.2 Pack and Unpack Domain

The domain structure is expected to be copied to the second server during domain creation. To copy the same, you can use pack and unpack utility provided under \$WLSHOME/common/bin.

Pack

Pack domain in primary server:

```
./pack.sh -managed=true -domain=/scratch/app/wl14c/user_projects/domains/ELCMDomain  
template=/tmp/ELCMDomain.jar -template_name="ELCMDomain"
```

Unpack

Unpack FTP FCBUSDomain.jar in binary mode to secondary server under /tmp area and unpack the domain using unpack utility provided under \$WLSHOME/common/bin

```
./unpack.sh -domain=/scratch/app/wl14c/user_projects/domains/ELCMDomain  
template=/tmp/ELCMDomain.jar
```

2.3 Start Admin server

Admin server is started on the primary server. Login to primary server and navigate to folder \$DOMAIN_HOME/bin and execute **startWeblogic.sh**.

2.4 Start Node Manager

Node Manager needs to be started on both the servers. Before starting the node manager update ListenAddress to the Hostname/IP Address of the machine in nodemanager.properties located in folder \$DOMAIN_HOME/nodemanager

To start the node manager login to the servers and navigate to folder \$DOMAIN_HOME/bin and execute **NodeManager.sh**

3.Cluster Configuration

Dynamic Cluster configuration involves below steps

- 1) Machine Configuration
- 2) Dynamic Cluster Creation: In a normal WebLogic Cluster you define Managed Server and add them to Cluster. In Dynamic Cluster, you select number of Servers you want in Cluster and Server Template you wish to assign to Servers in this WebLogic Dynamic Cluster.
- 3) Server template modification: Servers (or Managed Server) that are part of WebLogic Dynamic Cluster will have properties taken from Server Template.

Modify server template for best practices parameters for Dynamic Servers (part of Dynamic Cluster), you modify Server Template that is applicable to Dynamic Cluster. These settings are applicable to all the managed servers.

- 4) Activate Changes which would automatically create the managed servers (as mentioned in the number of servers required parameter).

Calculate Number of Servers Required:


For every 50 logged in ELCM users require one managed server of size 8GB. i.e. for 300 logged in ELCM users, it is recommended to have 6 managed servers. Based on the logged in users that needs to be supported decide on the number of the managed servers required. This parameter is required later in the dynamic cluster creation.

3.1 Machines Configuration


- 1) Login into Admin Console and navigate to **ELCMDomain** → **Environment** → **Machine** and click **New**.



2) Enter the **Machine Name** and click **Next**.



3) Enter the **Listen Address** and **Listen Port** (this is the port mentioned in nodemanager.properties file) and click **Finish**.



4) Machine is created.




5) Similarly create a new machine entry for the other server.



Verifying machine status

Before starting the managed servers, ensure that the Node manager Status of all the machines are "Reachable".

In the console, navigate through **Domain structure** → **Machines** → **machine1** → **Monitoring** → **Node Manager Status**. Status should be **Reachable**.




3.2 Dynamic Cluster Creation


- 1) Login into Admin Console and Navigate to **ELCMDomain** → **Environment** → **Clusters** → **New** → select **Dynamic Cluster**.



2) Enter the **Cluster Name** and click on **Next**.




3) Enter the **number of dynamic servers** you want to configure, enter the **server name prefix** and click on **Next**.




- 4) Select machines that participate in domain, in this case all machines will be part of the domain, select **Use any machine configured in this domain** option and click on **Next**.




- 5) Select the **listen port for the first server** in the dynamic cluster and then the **SSL listener port** for the first server in the dynamic cluster. The subsequent servers will be assigned with an incremental port number. Click **Next**.




- 6) A summary of new Dynamic Cluster Configuration is presented. Click **Finish** to create Dynamic Cluster.




- 7) The **Summary of Clusters** screens should show the recently created Dynamic Cluster.



- 8) Upon **Activate Changes** would automatically create 4 managed servers.



9) Navigate to **ELCMDomain** → **Environment** → **Servers** tab and 4 new servers are created.



3.3 Managed Server Template configuration

The server template created is modified to apply the below parameters:

3.3.1 Logging

The process of log file writing in a Weblogic server can impact the performance. Hence, you need to keep the logging to minimum in a production environment.

Update below parameters by in Logging Screen

Minimum Severity to log	Warning
Log file Severity level	Warning
Standard Out Severity level	Critical
Domain broadcaster Severity level	Critical

1) Navigate to ELCMDomain → Environment → Clusters.



2) Select ELCMTemplate and navigate to Logging → General.



3) Under Advanced tab, update the below parameters and click on Save.



Log file :

Severity level:	Warning	The minimum severity of log messages going to the server log file. By default all messages go to the log file. More Info...
Filter:	None	The filter configuration for the server log file. More Info...
Log File Buffer:	8	Gets the underlying log buffer size in kilobytes. More Info...
Standard out :		
Severity level:	Critical	The minimum severity of log messages going to the standard out. Messages with a lower severity than the specified value will not be published to standard out. More Info...
Filter:	None	The filter configuration for log events being sent to the standard out. More Info...
Domain log broadcaster :		
Severity level:	Critical	The minimum severity of log messages going to the domain log from this server's log broadcaster. Messages with a lower severity than the specified value will not be published to the domain log. More Info...
Filter:	None	The filter configuration for log events being sent to the domain log. More Info...
Buffer Size:	10	Broadcasts log messages to the domain log in batch mode. More Info...
<input checked="" type="checkbox"/> Stack Traces to stdout		Specifies whether to dump stack traces to the console when included in logged message. More Info...
stdout Stack Trace Depth:	5	Determines the no of stacktrace frames to display on standard out. All frames are displayed in the log file. '-' means all frames are displayed. More Info...
stdout Format:	standard	The output format to use when logging to the console. More Info...
<input type="button" value="Save"/>		

3.3.2 HTTP Logging

- 1) ELCMDomain → Environment → Clusters → ELCMTemplate → Logging → HTTP → Uncheck the Access Logs Flag.

Home Log Out Preferences Record Help Welcome, weblogic Connected to: FCUBSDoma

Home > FCUBSMSTemplate > Summary of Server Templates > FCUBSMSTemplate

Settings for FCUBSMSTemplate

Configuration Protocols **Logging** Debug Notes

General **HTTP** Data Source Diagnostic Images

Use this page to configure HTTP logging for the server. By default, HTTP logging is enabled and the server saves HTTP requests in a separate log file; it does not store HTTP requests in the server log file or the domain log file.

<input type="checkbox"/> HTTP access log file enabled	Indicates whether this server logs HTTP requests. (The remaining fields on this page are relevant only if you select this check box.) More Info...	
Log file name:	logs/access.log	The name of the log file. More Info...
Rotation		
Rotation type:	By Size	Criteria for moving old log messages to a separate file. More Info...
Rotation file size:	5000	The size (1 - 2097150 kilobytes) that triggers the server to move log messages to a separate file. The default is 500 kilobytes. After the log file

3.3.3 Stuck Thread Max Time

- 1) ELCMDomain → Environment → Clusters → ELCMTemplate → Tuning, update the stuck thread max time to 18000 and Click on Save.

3.4 Quartz Properties

1. `org.quartz.scheduler.instanceId = AUTO`
2. `org.quartz.jobStore.isClustered = true`
3. `org.quartz.jobStore.clusterCheckinInterval = 20000`

4.Tuning

4.1 General Parameters

PARAMETER	VALUE	Navigate To
JTA Time out seconds	18000	Login to Weblogic Server console. Click on the domain name (ex: ELCMDomain) which is under 'Domain Structure'. Go to Configuration > JTA, parameter and values is found on the right side panel of console.
Session Timeout	900	Login to Weblogic Server console Click on Deployments which is under 'Domain Structure'. Click on the deployed FCJ application from right side panel. Click on FCJNeoWeb from 'Modules and components' Go to Configuration General, the parameter values can be found here.

4.2 JVM Tuning

This section of the document provides JVM optimization for Oracle ELCM Universal Banking Solution.

Basically the JAVA minimum and maximum heap size needs to be reset for 32 and 64 bit environments. Both the minimum and maximum heap size is set to 1.5GB and 4GB in case of 32 bit and 64 bit environments respectively.

How to find whether the JVM is 32bit or 64bit?

Go to \$JAVA_HOME/bin directory. Check java version using command `./java -d64 -version` 64 bit JVM shows the version details where as 32bit throws an error.

How to modify the JVM heap parameters?

To change the JVM heap parameters create a file setUserOverrides.sh under domain ELCMCL in both servers. This file should be created in “\$WL_HOME/user_projects/domains/\$WLS_DOMAIN/bin” in both the servers. Paste below contents of USER_MEM_ARGS variable accordingly to override the standard memory arguments passed to java for **SUN JDK. 32 bit JDK**

```
USER_MEM_ARGS="-  
Dorg.apache.xml.dtm.DTManager=org.apache.xml.dtm.ref.DTManagerDefault  
-  
Dorg.apache.xerces.xni.parser.XMLParserConfiguration=org.apache.xerces.  
parsers.XML11Configuration -Dweblogic.threadpool.MinPoolSize=100 -  
Dweblogic.threadpool.MaxPoolSize=100 -Xms1536M -Xmx1536M -  
XX:MaxPermSize=256m -server -XX:+UseParallelOldGC -  
XX:ParallelGCThreads=4" export  
USER_MEM_ARGS
```

64 bit JDK

```
USER_MEM_ARGS="-  
Dorg.apache.xml.dtm.DTManager=org.apache.xml.dtm.ref.DTManagerDefault  
-Dorg.a  
pache.xerces.xni.parser.XMLParserConfiguration=org.apache.xerces.parser  
s.XML11Configuration -Dweblogic.threadpool.MinPoolSize=100 -  
Dweblogic.threadpool.MaxPoolSize=100 -Xms8g -Xmx8g -Xmn4g -server  
-XX:+UseParallelOldGC -XX:ParallelGCThreads=4" export  
USER_MEM_ARGS
```

Note: Take a backup of the files before modifying the same.

5.Start Managed Servers

Starting using scripts

Managed Servers can be started by executing startManagedWebLogic.sh script present in folder **\$DOMAIN_HOME/bin**

Usage: ./startManagedWebLogic.sh SERVER_NAME {ADMIN_URL}

Eg: ./startManagedWeblogic.sh ELCMMS1 https://<hostname1>/console

Starting using console

Alternatively, login to admin console, navigate to **ELCMDomain → Environment → Servers → Control**, select the managed servers to be started and click on **Start**.

The screenshot shows the Oracle WebLogic Server Administration Console. The 'Summary of Servers' page is displayed, with the 'Control' tab selected. A table lists the servers and their status. A red box highlights the 'Start' button for the selected servers.

Server ID	Machine	State	Status of Last Action
AdminServer(admin)		RUNNING	None
FC_EBPS1	Machine1	SHUTDOWN	None
FC_EBPS2	Machine2	SHUTDOWN	None
FC_EBPS3	Machine1	SHUTDOWN	None
FC_EBPS4	Machine2	SHUTDOWN	None

Upon successful startup, the status of Managed servers is changed to **“RUNNING”**.

6.Data Source creation and JDBC Configuration

Following are the JNDI names of those data sources used by ELCM application.

jdbc/fcjdevDS - This datasource is used by ELCM online screen excluding branch screens.


- jdbc/fcjdevDSBranch - This datasource is used by Branch screens.
- jdbc/fcjSchedulerDS - This datasource is used by Quartz scheduler.

Note:

- jdbc/fcjdevDS should be **NonXA**.
- jdbc/fcjdevDSBranch and jdbc/fcjSchedulerDS should be **XA**

6.1 Data source creation: non XA

- 1) Navigate to **ELCMDomain** → **Services** → **Data Sources** → select **New > Generic Data Source**.



- 2) Enter the **Name** and **JNDI Name** and Click on **Next**

ORACLE WebLogic Server Administration Console 12c

Home | Home | Log Out | Preferences | Recent Web | Welcome, weblogic | Connected to: FCUBSDomain

Home > FCUBSDomain > Summary of Services > Templates > FCUBSDomain > Summary of Quotas > Summary of Services > Summary of JDBC Data Sources

Create a New JDBC Data Source

Back | Next | Finish | Cancel

JDBC Data Source Properties

The following properties will be used to identify your new JDBC data source.
* Indicates required fields.

What would you like to name your new JDBC data source?

Name:

What JNDI name would you like to assign to your new JDBC Data Source?

JNDI Name:

What database type would you like to select?

Database Type:

Back | Next | Finish | Cancel

Change Center

View changes and restarts

No pending changes exist. Click the Release Configuration button to allow others to edit the domain.

Lock & Edit
Release Configuration

Domain Structure

FCUBSDomain

- Environment
 - Servers
 - Clusters
 - Server Templates
 - Migrateable Targets
 - Coherence Clusters
 - Modules
 - Virtual Hosts
 - Work Managers
 - Startup and Shutdown Classes
 - Deployments
 - Services
 - IT Resources

How do I...


- Create JDBC generic data sources
- Create J2EE-enabled JDBC data sources

System Status

Health of Running Servers

Failed (0)


- 3) Select the Driver as **Oracle's Driver(thin)** for Instance connection: **Versions: Any** and Click on **Next**.



- 4) Uncheck the **Supports Global Transactions** and click on **Next**.



- 5) Enter the **Database Name, Host Name, Port, Database User Name, Password, Confirm Password** and click on **Next**.



6) Replace the **JDBC URL** in the below format and click on **Next**.

Default URL: jdbc:oracle:thin:@<IP_Address>:<Port>:<INSTANCE_NAME>.

Change the default URL to:

```
jdbc:oracle:thin:@(DESCRIPTION=(ADDRESS_LIST=(ADDRESS=(PROTOCOL=TCP)(HOST=xxxxxx.com)(PORT=1521)))(CONNECT_DATA=(SERVICE_NAME=ELCM)))
```

Where,


Scan IP = xxxxxx.com

Service Name = ELCM

Port = 1521

Make sure that in URL, we make the necessary changes.

Then Click on Test Configuration. The connection test should be successful.




7) Select Target as **ELCMCluster** and click on **Finish**.




6.2 XA Datasource

1) Navigate to **ELCMDomain** → **Services** → **Data Sources** → select **New** > **Generic Data Source**.



2) Enter the **Name** and **JNDI Name** and Click on **Next**.





3) Select the Driver as **Oracle's Driver(thin XA) for Instance connection: Versions: Any** and Click on **Next**.



4) Click on **Next**.



5) From this step to target setting step follow as mentioned in non-xa.






6) Upon **Activate Changes** would create the XA Datasource.



7) Similarly create all the other Data Source required for the ELCM Application and Gateway Deployments.



6.3 JDBC Parameters Tuning

Below JDBC parameters needs to updated for all the Datasources.

PARAMETER	VALUE	Navigate To
Connection Reserve time out	30	Connection Pool->Advance
Test Frequency	60	Connection Pool->Advance
Inactive connection time out	30	Connection Pool->Advance
Initial Capacity	1	Connection Pool
Max capacity	Based on Site Requirement	Connection Pool
Capacity Increment	5	Connection Pool
Shrink Frequency	900	Connection Pool->Advance
Test Connection on Reserve	Checked	Connection Pool->Advance
Statement Cache Size	50	Connection Pool

7.JMS Resource Creation

JMS Resource Creation involves various steps:

- Persistence Store Creation
- JMS Server Creation
- JMS Module Creation
- Resource Creation: Connection Factory and Queue's

Refer to the [Configuring JMS on Weblogic Server](#) for further details on JMS setup.

8.Oracle WebLogic Load Balancing

For Weblogic Load balancing, use

- 1) Oracle HTTP Server: Refer to Configuration for Oracle HTTP Server for setup.
- 2) Apache: Refer to Configuration for Apache for setup.

9. Frequently Asked Questions

9.1 Machine status is Unreachable

If the machine status is unreachable, means that machine is not reachable and from console you cannot start/stop the managed servers.

In the console, navigate through Domain structure → Machines → machine1 → Monitoring → Node Manager Status will be **Unreachable**.

To change the status, you need to start the node manager on that server. Refer to start node manager section on steps to start the node manager.


9.2 How to restart node manager?

- 1) Locate node manager pid using `ps -ef|grep weblogic.nodemanager.javaHome`
- 2) Change directory to `$DOMAIN_HOME/bin`
- 3) Kill the unix process using `kill -9 <pid>`
- 4) Verify that the node manager is killed by `tail -f nohup.out`
- 5) Start node manager using `nohup ./startNodeManager.sh &`
- 6) Verify nodemanager is started using `tail -f nohup.out`

9.3 Scaling Up Dynamic Cluster

When the capacity is insufficient and you need to scale-up, you can add dynamic servers on demand. It requires only a few clicks.


- 1) Navigate to **ELCMDomain → Environment → Clusters**.



- 2) Click **ELCMCluster → Configuration → Servers** tab.



3) Change the **Maximum Number of Dynamic Servers** to 8. Click **Save**.



4) Activate changes in the **Change Center** of the Weblogic Console. After activation, 4 new Dynamic Servers are added to the Dynamic Cluster.

Name	Type	Machine	Listen Port
FCUBSM51	Dynamic	MAC-1	7101
FCUBSM52	Dynamic	MAC-2	7102
FCUBSM53	Dynamic	MAC-1	7103
FCUBSM54	Dynamic	MAC-2	7104
FCUBSM55	Dynamic	MAC-1	7105
FCUBSM56	Dynamic	MAC-2	7106
FCUBSM57	Dynamic	MAC-1	7107
FCUBSM58	Dynamic	MAC-2	7108

5) Start the 4 new Dynamic Servers and you have doubled your capacity.

9.4 Session Timeout

Session timeouts occur intermittently during load condition. Verify the following:

1. Clock Synchronization: Time across the nodes/machines is same.
2. Session Stickiness in load balancer: Persistence Type in load balancer should be set to SOURCE IP and should not be cookie.



ELCM Weblogic 14c Middleware Practices
December 2023
Version 14.7.2.0.0

Oracle Financial Services Software Limited
Oracle Park
Off Western Express Highway
Goregaon (East)
Mumbai, Maharashtra 400 063 India

Worldwide Inquiries:
Phone: +91 22 6718 3000 Fax: +91 22 6718 3001
<https://www.oracle.com/industries/financial-services/index.html>

Copyright © 2007, 2023, Oracle and/or its affiliates. All rights reserved.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate failsafe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

This software or hardware and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.