

**Oracle® Communications  
Convergent Charging Controller**

ACS Provisioning Interface Commands

Release 12.0.0

December 2017

# Copyright

Copyright © 2017, Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

# Contents

About This Document .....	v
Document Conventions .....	vi
<b>Chapter 1</b>	
<b>PI Commands Overview .....</b>	<b>1</b>
Overview .....	1
Command List .....	1
About Service Provider Restrictions .....	2
<b>Chapter 2</b>	
<b>piAcsSms Package .....</b>	<b>3</b>
Overview .....	3
Adding a CLI to ACS Numbers by Using PI .....	3
Deleting a CLI From ACS Numbers .....	4
Querying a CLI in ACS Numbers .....	5
Exporting a Control Plan .....	5
Importing a Control Plan .....	6
Deleting a Control Plan .....	7
Adding an ACS Customer .....	8
Querying an ACS Customer .....	10
Changing a Profile Entry .....	10
Querying a Profile Entry .....	13
Adding Customer Service Numbers .....	15
Changing the Scheduled Control Plan .....	16
Querying Customer Service Numbers .....	17
Deleting Customer Service Numbers .....	17
Adding Customer Termination Numbers .....	18
Querying Customer Termination Numbers .....	19
Deleting Customer Termination Numbers .....	20
Managing FCI Data by Using PI .....	21
<b>Chapter 3</b>	
<b>Error Code Lists .....</b>	<b>23</b>
Overview .....	23
PI Chassis Errors .....	23
PI Command Errors .....	24
<b>Glossary of Terms .....</b>	<b>29</b>
<b>Index .....</b>	<b>31</b>



# About This Document

## Scope

The scope of this document includes all the information required to configure the Provisioning Interface commands.

## Audience

The audience for this document includes system administrators responsible for the monitoring, maintenance, and configuration of the Oracle Communications Convergent Charging Controller IN applications.

## Prerequisites

A solid understanding of UNIX and a familiarity with IN concepts are an essential prerequisite for safely using the information contained in this technical guide.

Although it is not a prerequisite to using this guide, familiarity with the target platform would be an advantage.

This manual describes system tasks that should only be carried out by suitably trained operators.

## Related Documents

The following documents are related to this document:

- *Provisioning Interface User's and Technical Guide*
- *Virtual Private Network User's Guide*
- *Charging Control Services Provisioning Interface Commands*

# Document Conventions

## Typographical Conventions

The following terms and typographical conventions are used in the Oracle Communications Convergent Charging Controller documentation.

Formatting Convention	Type of Information
<b>Special Bold</b>	Items you must select, such as names of tabs. Names of database tables and fields.
<i>Italics</i>	Name of a document, chapter, topic or other publication. Emphasis within text.
<b>Button</b>	The name of a button to click or a key to press. <b>Example:</b> To close the window, either click <b>Close</b> , or press <b>Esc</b> .
<b>Key+Key</b>	Key combinations for which the user must press and hold down one key and then press another. Example: <b>Ctrl+P</b> or <b>Alt+F4</b> .
Monospace	Examples of code or standard output.
<b>Monospace Bold</b>	Text that you must enter.
<i>variable</i>	Used to indicate variables or text that should be replaced with an actual value.
<b>menu option &gt; menu option &gt;</b>	Used to indicate the cascading menu option to be selected. Example: <b>Operator Functions &gt; Report Functions</b>
<a href="#">hypertext link</a>	Used to indicate a hypertext link.

Specialized terms and acronyms are defined in the glossary at the end of this guide.

# PI Commands Overview

## Overview

### Introduction

The provisioning interface (PI) uses TCP/IP-based UNIX sockets to receive provisioning commands and parameters. These are translated into SQL commands that update prepaid application tables of the SMF and E2BE Oracle databases. This chapter defines the rules and packages required to translate the provisioning commands into SQL commands.

### In this chapter

---

This chapter contains the following topics.

Command List .....	1
About Service Provider Restrictions .....	2

## Command List

### ACS PI Command List

The following table lists the ACS PI functions and their corresponding commands. To use these commands, the `piAcsSms` package must be installed.

Function	PI Command
Add CLI to ACS Numbers	ACSCLI=ADD
Delete a CLI from ACS Numbers	ACSCLI=DEL
Query a CLI using ACS Numbers	ACSCLI=QRY
Export a control plan for an ACS customer.	ACSCPL=EXP
Import a control plan for an ACS customer.	ACSCPL=IMP
Delete a control plan for an ACS customer.	ACSCPL=DEL
Add an ACS customer.	ACSCST=ADD
Query an ACS customer.	ACSCST=QRY
Change a profile entry.	ACSPFL=CHG
Query a profile entry.	ACSPFL=QRY
Add a service number and associated control plan for a customer.	ACSSNM=ADD
Change the scheduled a control plan for a service number.	ACSSNM=CHG
Query a service number for a customer.	ACSSNM=QRY
Delete a service number and associated control plan for a customer.	ACSSNM=DEL
Add a termination number for a customer.	ACSTNM=ADD
Query a termination number for a customer.	ACSTNM=QRY
Delete a termination number for a customer.	ACSTNM=DEL

## About Service Provider Restrictions

For security reasons, the data that a PI user can query or modify is restricted by service provider. This means that you can run PI commands to query or modify the data only for a service provider that is associated with your PI user.

The system administrator specifies which service providers to associate with your PI user on the **Users** tab in the Administration screen in the PI UI. For more information, see *PI User's and Technical Guide*.

Attempts to run PI commands for a service provider that is not associated with your PI user will result in a negative acknowledgement (NACK) message being returned.



# piAcsSms Package

## Overview

### Introduction

This chapter describes the available PI commands for provisioning ACS customers, CLIs, and profile entries on the SMS.

These commands are added by the `piAcsSms` package that is installed when you install Convergent Charging Controller. For more information about the installed PI packages, see *PI User's and Technical Guide*.

### In this chapter

---

This chapter contains the following topics.

Adding a CLI to ACS Numbers by Using PI .....	3
Deleting a CLI From ACS Numbers .....	4
Querying a CLI in ACS Numbers .....	5
Exporting a Control Plan.....	5
Importing a Control Plan.....	6
Deleting a Control Plan.....	7
Adding an ACS Customer .....	8
Querying an ACS Customer .....	10
Changing a Profile Entry.....	10
Querying a Profile Entry .....	13
Adding Customer Service Numbers .....	15
Changing the Scheduled Control Plan .....	16
Querying Customer Service Numbers.....	17
Deleting Customer Service Numbers .....	17
Adding Customer Termination Numbers.....	18
Querying Customer Termination Numbers.....	19
Deleting Customer Termination Numbers .....	20
Managing FCI Data by Using PI.....	21

## Adding a CLI to ACS Numbers by Using PI

### About Adding a CLI to ACS Numbers by Using PI

Use the `ACSCLI=ADD` PI command to add a new CLI in ACS Numbers, and to schedule the specified control plan for the CLI. Specify an existing CLI to update the CLI with new data.

**Note:** You must specify an existing control plan in the `CALLPLAN` parameter.

You can also set the list of allowed numbers for the CLI by specifying the optional `ALLOWED` parameter. If you do not specify `ALLOWED`, then the PI sets the `IGNORE` flag for the number list.

After successfully adding a CLI to ACS Numbers, the PI returns this message:

```
ACSCLI=ADD:ACK;
```

If unsuccessful, the PI may return these error codes: 101, 102, 103, 105, 106, 107, 108, 109 and 110.

### Required Parameters

Here are the required parameters for this command.

CLI

**Syntax:** CLI=*num*  
**Description:** CLI for the subscriber.  
**Format:** 18-digit number (greater than 0)  
**Example:** CLI=1234567

CALLPLAN

**Syntax:** CALLPLAN=*cp*  
**Description:** The name of the control plan for the service.  
**Format:** 50 character string  
**Example:** CALLPLAN=CP2

### Optional Parameters

ACSCLI=ADD accepts the following optional parameters.

#### ALLOWED

**Syntax:** ALLOWED="*cell | cell | ...*"  
**Description:** A pipe (|) separated list of up to 100 *cells*, where each *cell* value is an allowed number for the CLI.  
**Format:** "*CELL1|CELL2...*"  
**Note:** Each *cell* value is a 15-digit number (zero padded), formatted as follows:  
*MSCID + ServingCellID*  
Where:

- *MSCID* (Optional) consists of a six digit market ID followed by a three digit switch number
- *ServingCellID* is a six digit number

**Example:** ALLOWED="123456789012345 | 223456789012345"

## Deleting a CLI From ACS Numbers

### About Deleting a CLI in ACS Numbers by Using PI

Use the ACSCLI=DEL PI command to delete a CLI from ACS Numbers. Deleting the CLI also un-schedules any control plans that are scheduled for the CLI.

After successfully deleting a CLI from ACS Numbers, the PI returns this message:

```
ACSCLI=DEL:ACK;
```

If unsuccessful, the PI may return these error codes: 101, 102, 104, 105, 107, 108, 109 and 110.

## Required Parameter

Here is the required parameter for this command.

CLI

<b>Syntax:</b>	CLI= <i>num</i>
<b>Description:</b>	The CLI for the subscriber. The CLI must exist already.
<b>Format:</b>	18-digit number (greater than 0)
<b>Example:</b>	CLI=1234567

## Querying a CLI in ACS Numbers

### About Querying a CLI in ACS Numbers by Using PI

Use the ACSCLI=QRY:ACK:ALLOWED=*cell1* | *cell2* | ...; command to query the ACS Numbers data for the list of allowed numbers for a specified CLI.

After successfully querying a CLI in ACS Numbers, the PI returns this message:

```
ACSCLI=QRY:ACK:ALLOWED=cell1 | cell2 | ...;
```

Where *cell* is a number from the allowed numbers list for the CLI. For details about *cell* number formats, see *ALLOWED* (on page 4) parameter description.

If unsuccessful, the PI may return these error codes: 101, 102, 104, 105, 107 and 109.

## Required Parameter

Here is the required parameter for this command.

CLI

<b>Syntax:</b>	CLI= <i>num</i>
<b>Description:</b>	The CLI for the subscriber. The CLI must exist already.
<b>Format:</b>	18-digit number (greater than 0)
<b>Example:</b>	CLI=1234567

## Exporting a Control Plan

### About Exporting a Control Plan by Using PI

Use the ACSCPL=EXP:CUSTOMER=*Telco*, CALLPLAN=*Postpaid*; command to export a control plan for a specified ACS customer to a .cpl file. For example, the following PI command exports the Postpaid control plan for the Telco customer:

```
ACSCPL=EXP:CUSTOMER=Telco, CALLPLAN=Postpaid;
```

The PI exports the control plan to the following directory by default:

```
/IN/service_packages/PI/callplans
```

You can set a different control plan export directory by configuring the `exportCallPlanDirectory` parameter in the `pi`, `ACSCPL` section of the `eserv.config` configuration file. See *PI User's and Technical Guide* for more information.

After successfully exporting a control plan, the PI returns this message:

## Chapter 2

```
ACSCPL=EXP:FILENAME=export_path/filename;
```

Where:

- *export\_path* is the full directory path for the exported control plan file on the SMS; for example, `/IN/service_packages/callplans`
- *filename* has the following format, based on the customer name, control plan name and control plan version number: *customer\_\_controlplan\_\_version.cpl*; for example, `Telco__Postpaid__1.cpl`

If unsuccessful, the PI may return these error codes: 101, 102, 103, 107, and 118.

### Required Parameters

Here are the required parameters for this command.

CUSTOMER

**Syntax:** CUSTOMER=*name*  
**Description:** The name of an existing customer.  
**Type:** String  
**Optionality:** Required  
**Allowed:** A string of up to 50 characters.  
**Example:** CUSTOMER=Customer A

CALLPLAN

**Syntax:** CALLPLAN=*string*  
**Description:** The name of the control plan. You must specify an existing control plan that belongs to the specified customer.  
**Type:** String  
**Optionality:** Required  
**Allowed:** A string of up to 50 characters.  
**Example:** CALLPLAN=Control Plan 2

## Importing a Control Plan

### About Importing a Control Plan by Using PI

Use the ACSCPL=IMP PI command to import a control plan for a specified ACS customer from a `.cpl` file, and to compile the control plan after it is imported. For example, the following PI command imports the Postpaid control plan for the Telco customer from the `Postpaid_test.cpl` file:

```
ACSCPL=IMP:CUSTOMER=Telco, CALLPLAN=Postpaid, FILENAME=/IN/service_packages/PI/callplans/Postpaid_test.cpl;
```

If the control plan:

- Does not exist for the specified customer, then the PI creates a new control plan and sets its version number to 1 (one)
- Already exists for the specified customer, then the PI updates the control plan and increments its version number, provided that:
  - Only a single successfully compiled version of the control plan exists
  - No other control plans use the control plan structure
  - The control plan is not associated with an ACS service number, an ACS CLI number, or a CCS product type

After successfully importing and compiling a control plan, the PI returns this message:

```
ACSCPL=IMP:ACK;
```

If unsuccessful, the PI may return these error codes: 101, 102, 107, 118, 120 and 121.

## Required Parameters

Here are the required parameters for this command.

### CUSTOMER

**Syntax:** CUSTOMER=*name*  
**Description:** The name of an existing customer.  
**Type:** String  
**Optionality:** Required  
**Allowed:** A string of up to 50 characters.  
**Example:** CUSTOMER=Customer A

### CALLPLAN

**Syntax:** CALLPLAN=*string*  
**Description:** The name that the new control plan will use.  
**Type:** String  
**Optionality:** Required  
**Allowed:** A string of up to 50 characters.  
**Example:** CALLPLAN=Control Plan 2

### FILENAME

**Syntax:** FILENAME=*string*  
**Description:** The name of the .cpl import file. Specify the filename by using the following format:  
*file\_name.cpl*  
 Where *file\_name* includes the full directory path of the .cpl import file on the SMS; for example, /IN/service\_packages/PI/callplans/Postpaid\_test.cpl.  
**Type:** String  
**Optionality:** Required  
**Example:** FILENAME=/IN/service\_packages/PI/callplans/Postpaid\_test.cpl

## Deleting a Control Plan

### About Deleting a Control Plan by Using PI

Use the ACSCPL=DEL PI command to delete a control plan for a specified ACS customer. For example, the following PI command deletes the Postpaid control plan for the Telco customer:

```
ACSCPL=DEL:CUSTOMER=Telco, CALLPLAN=Postpaid;
```

You can delete a control plan providing:

- Only one entry for the control plan exists in the database
- The control plan structure is not being used by other control plans

- The control plan is not associated with an ACS service number, an ACS CLI number, or a CCS product type

After successfully deleting a control plan, the PI returns this message:

```
ACSCPL=DEL:ACK;
```

If unsuccessful, the PI may return these error codes: 101, 102, 103, 107 and 118.

### Required Parameters

Here are the required parameters for this command.

CUSTOMER

<b>Syntax:</b>	CUSTOMER= <i>name</i>
<b>Description:</b>	The name of an existing customer.
<b>Type:</b>	String
<b>Optionality:</b>	Required
<b>Allowed:</b>	A string of up to 50 characters.
<b>Example:</b>	CUSTOMER=Customer A

CALLPLAN

<b>Syntax:</b>	CALLPLAN= <i>string</i>
<b>Description:</b>	The name of the control plan. You must specify an existing control plan that belongs to the specified customer.
<b>Type:</b>	String
<b>Optionality:</b>	Required
<b>Allowed:</b>	A string of up to 50 characters.
<b>Example:</b>	CALLPLAN=Control Plan 2

## Adding an ACS Customer

### About Adding an ACS Customer by Using PI

Use the ACSCST=ADD PI command to add an ACS customer to the database.

To successfully add a customer, your PI user must be associated with the default service provider named "Boss". A negative acknowledgement (NACK) is returned if you attempt to add a customer and your PI user is not associated with the "Boss" service provider. See *About Service Provider Restrictions* (on page 2) for more information.

**Note:** The "Boss" service provider is automatically created at installation.

After successfully adding a customer, the PI returns this message:

```
ACSCST=ADD:ACK;
```

If unsuccessful, the PI can return any of the following error codes: 136, 137, 138, 140, or 142.

### Required Parameters

Here are the required parameters for this command.

CUSTOMER

<b>Syntax:</b>	CUSTOMER= <i>name</i>
<b>Description:</b>	The name of the customer to add.

**Type:** String  
**Optionality:** Required.  
**Allowed:** A string of up to 50 characters.  
**Example:** CUSTOMER=Customer A

#### PARENT

**Syntax:** PARENT=*string*  
**Description:** The name of the customer's parent customer.  
**Type:** String  
**Optionality:** Required if the RESELLER\_FLAG is set to A. The parent customer must be a reseller.  
 Optional if the RESELLER\_FLAG is set to N or null.  
 If RESELLER\_FLAG is set to R, then you cannot set the parent customer.  
**Allowed:** A string of up to 50 characters.  
**Example:** PARENT=Customer A

## Optional Parameters

ACSCST=ADD accepts the following optional parameters.

#### DESCRIPTION

**Syntax:** DESCRIPTION=*string*  
**Description:** The customer's description.  
**Type:** String  
**Optionality:** Optional.  
**Allowed:** A string of up to 2000 characters.  
**Example:** DESCRIPTION=A customer description

#### CUSTOMER\_REFERENCE

**Syntax:** CUSTOMER\_REFERENCE=*string*  
**Description:** The customer reference ID.  
**Type:** String  
**Optionality:** Optional  
**Allowed:** A string of up to 749 characters.  
**Example:** CUSTOMER\_REFERENCE=CRX001A

#### TELCO\_MANAGED

**Syntax:** TELCO\_MANAGED=Y|N  
**Description:** Specifies whether the customer is managed by the operator.  
**Type:** Boolean  
**Optionality:** Optional (default used if not set).  
**Allowed:** Y – The customer is managed by the operator.  
 N – The customer is not managed by the operator.  
**Default:** Y  
**Example:** TELCO\_MANAGED=N

### RESELLER\_FLAG

<b>Syntax:</b>	RESELLER_FLAG=N R A
<b>Description:</b>	Defines whether or not the customer is a reseller or an agent.
<b>Type:</b>	String
<b>Optionality:</b>	Optional (default used if not set).
<b>Allowed:</b>	N – The customer is not a reseller or an agent. R – The customer is a reseller. A – The customer is an agent.
<b>Default:</b>	N
<b>Example:</b>	RESELLER_FLAG=N

## Querying an ACS Customer

### About Querying an ACS Customer by Using PI

Use the ACSCST=QRY PI command to query the database for the details of the specified ACS customer. After successfully performing a customer query, the PI returns this message:

```
ACSCST=QRY:ACK:  
  CUSTOMER=name, DESCRIPTION=customer_description,  
  CUSTOMER_REFERENCE=customer_reference, TELCO_MAN=Y|N, RESELLER_FLAG=N|R|A,  
  [PARENT=parent_name]
```

Where:

- *name* is the name of the customer.
- *customer\_description* is the description for the customer.
- *customer\_reference* is the customer reference ID.
- *parent\_name* is name of the customer's parent. No value is returned when the operator is the customer's parent.

If the PI fails to find the specified customer, then the PI returns error code 118.

### Required Parameter

Here is the required parameter for this command.

#### CUSTOMER

<b>Syntax:</b>	CUSTOMER= <i>name</i>
<b>Description:</b>	The name of an existing customer.
<b>Type:</b>	String
<b>Optionality:</b>	Required
<b>Allowed:</b>	A string of up to 50 characters.
<b>Example:</b>	CUSTOMER=Customer A

## Changing a Profile Entry

### About Changing a Profile Entry by Using PI

Use the ACSPFL=CHG PI command to change a profile entry in the database. After successfully changing a profile entry, the PI returns this message:



ACSPFL=CHG:ACK;

If unsuccessful, then the PI may return these error codes: 101, 102, 107, 110, 111, 112, 113, 114, 115, 116 and 117.

## Required Parameters

Here are the required parameters for this command.

### TABLE

**Syntax:** TABLE=*table*  
**Description:** The name of the profile table that holds the profile entry you want to change or query. You must specify an existing profile table.  
**Type:** 30-character string  
**Example:** TABLE=ACS\_PROFILE\_DETAILS

### ID

**Syntax:** ID=*id*  
**Description:** The ID of the row.  
**Type:** Integer  
**Example:** ID=45

### TAG

**Syntax:** TAG=*tag\_id*  
**Description:** The profile tag.  
**Type:** Hex or String  
**Allowed:** Either a hexadecimal value prefixed by 0x, for example, 0x123ABC or a pre-defined name corresponding to PROFILE\_TAG\_NAME in the ACS\_PROFILE\_DETAILS table.  
**Default:** HEX  
**Notes:** If TAG is:

- A predefined name, any specified TYPE is ignored
- A hexadecimal value, and TYPE is omitted, the value will be returned as hexadecimal data
- Omitted, a hex dump of the whole profile is returned

**Example:** TAG=0x123ABC

## Optional Parameters

The ACSPFL=CHG PI command accepts the following optional parameters.

### PROFILE\_COL

**Syntax:** PROFILE\_COL=*column\_name*  
**Description:** The name of the profile column.  
**Type:** String  
**Optionality:** Optional (default used if omitted)  
**Allowed:** A valid profile column name from the specified profile table.  
**Default:** PROFILE  
**Example:** PROFILE\_COL=CLI

## Chapter 2

### ID\_COL

**Syntax:** ID\_COL=*id\_col\_name*  
**Description:** The name of the ID column.  
**Type:** String  
**Optionality:** Optional (default used if omitted).  
**Allowed:** ID  
**Default:** ID  
**Notes:** A valid column in TABLE containing unique ID.  
**Example:** ID\_COL=ID

### TYPE

**Syntax:** TYPE=*tag\_type*  
**Description:** The type of the tag.  
**Type:** String  
**Optionality:** Optional (default used if omitted).  
**Allowed:** Valid options are:

- STRING – String value
- DATE – Date value
- INTEGER – 32-bit signed integer value
- HEX – Raw hexadecimal data
- TN – Telephone number

**Default:** HEX  
**Notes:** DATE type values have the following format: YYYYDDMMHHMMSS; for example, 20131609100500.  
**Example:** TYPE=DATE

### VALUE

**Syntax:** VALUE=*val*  
**Description:** The value of the tag.  
**Type:** Defined by the TYPE parameter.  
**Optionality:** Optional  
**Allowed:**  
**Default:** If VALUE is not specified, any existing profile tag will be deleted.  
**Notes:** For TYPE = TN, the VALUE format:

- Must contain only numeric digits
- First character is interpreted as a TN type
- TN type has range 0-5
- TN has max length 33 characters (including TN type)

**Examples:**

VALUE=12345	Integer type
VALUE=Monday	String type
VALUE=2009010112345	Date type (YYYYMMDDHHMMSS)
VALUE=0x123ABC	Hex type
VALUE=12345	TN type

## Querying a Profile Entry

### About Querying a Profile Entry by Using PI

Use the ACSPFL=QRY PI command to query a profile entry in the database.

After successfully querying a profile entry, the PI returns this message if TAG was specified:

- ACSPFL=QRY:ACK:TAG=*tag*,VALUE=*value*;
- ACSPFL=QRY:ACK:TAG=*tag*;

The PI returns this message if TAG was not specified:

- ACSPFL=QRY:ACK:  
TAG=*hex tag*,VALUE=*hex value*[,  
TAG=*hex tag*,VALUE=*hex value*[,  
...]];

**Note:** No carriage returns are returned.

If unsuccessful, then the PI may return these error codes: 101, 102, 107, 111, 112, 113, 114, 115 and 116.

### Required Parameters

Here are the required parameters for this command.

TABLE

<b>Syntax:</b>	TABLE= <i>table</i>
<b>Description:</b>	The name of the profile table that holds the profile entry you want to change or query. You must specify an existing profile table.
<b>Type:</b>	30-character string
<b>Example:</b>	TABLE=ACS_PROFILE_DETAILS

ID

<b>Syntax:</b>	ID= <i>id</i>
<b>Description:</b>	The ID of the row.
<b>Type:</b>	Integer
<b>Example:</b>	ID=45

### Optional Parameters

The ACSPFL=QRY PI command accepts the following optional parameters.

PROFILE\_COL

<b>Syntax:</b>	PROFILE_COL= <i>column_name</i>
<b>Description:</b>	The name of the profile column.
<b>Type:</b>	String
<b>Optionality:</b>	Optional (default used if omitted)
<b>Allowed:</b>	A valid profile column name from the specified profile table.
<b>Default:</b>	PROFILE
<b>Example:</b>	PROFILE_COL=CLI

## Chapter 2

### ID\_COL

<b>Syntax:</b>	<code>ID_COL=id_col_name</code>
<b>Description:</b>	The name of the ID column.
<b>Type:</b>	String
<b>Optionality:</b>	Optional (default used if omitted).
<b>Allowed:</b>	ID
<b>Default:</b>	ID
<b>Notes:</b>	A valid column in TABLE containing unique ID.
<b>Example:</b>	<code>ID_COL=ID</code>

### TAG

<b>Syntax:</b>	<code>TAG=tag_id</code>
<b>Description:</b>	The profile tag.
<b>Type:</b>	Hex or String
<b>Allowed:</b>	Either a hexadecimal value prefixed by 0x, for example, 0x123ABC or a pre-defined name corresponding to PROFILE_TAG_NAME in the ACS_PROFILE_DETAILS table.
<b>Default:</b>	HEX
<b>Notes:</b>	If TAG is: <ul style="list-style-type: none"><li>• A predefined name, any specified TYPE is ignored</li><li>• A hexadecimal value, and TYPE is omitted, the value will be returned as hexadecimal data</li><li>• Omitted, a hex dump of the whole profile is returned</li></ul>
<b>Example:</b>	<code>TAG=0x123ABC</code>

### TYPE

<b>Syntax:</b>	<code>TYPE=tag_type</code>
<b>Description:</b>	The type of the tag.
<b>Type:</b>	String
<b>Optionality:</b>	Optional (default used if omitted).
<b>Allowed:</b>	Valid options are: <ul style="list-style-type: none"><li>• STRING – String value</li><li>• DATE – Date value</li><li>• INTEGER – 32-bit signed integer value</li><li>• HEX – Raw hexadecimal data</li><li>• TN – Telephone number</li></ul>
<b>Default:</b>	HEX
<b>Notes:</b>	DATE type values have the following format: YYYYDDMMHHMMSS; for example, 20131609100500.
<b>Example:</b>	<code>TYPE=DATE</code>

## Adding Customer Service Numbers

### About Adding Customer Service Numbers by Using PI

Use the ACSSNM=ADD PI command to add a service number for a specified ACS customer. You can also use this command to add a scheduled control plan to the service number. After successfully adding a service number for a customer, the PI returns this message:

```
ACSSNM=ADD:ACK;
```

If unsuccessful, then the PI may return any of the following error codes: 118, 140, 141, or 143.

### Required Parameters

Here are the required parameters for this command.

#### CUSTOMER

<b>Syntax:</b>	CUSTOMER= <i>name</i>
<b>Description:</b>	The name of an existing customer.
<b>Type:</b>	String
<b>Optionality:</b>	Required
<b>Allowed:</b>	A string of up to 50 characters.
<b>Example:</b>	CUSTOMER=Customer A

#### SERVICE\_NUMBER

<b>Syntax:</b>	SERVICE_NUMBER= <i>string</i>
<b>Description:</b>	The service number to add or delete.
<b>Type:</b>	String
<b>Optionality:</b>	Required
<b>Allowed:</b>	A string of up to 32 characters. Valid characters are 0–9, A–F, *, #.
<b>Example:</b>	SERVICE_NUMBER=115

### Optional Parameter

The ACSSSN=ADD PI command accepts the following optional parameter.

#### CONTROLPLAN

<b>Syntax:</b>	CONTROLPLAN= <i>string</i>
<b>Description:</b>	The control plan name.
<b>Type:</b>	String
<b>Optionality:</b>	Optional
<b>Allowed:</b>	A string of up to 50 characters
<b>Example:</b>	CONTROLPLAN=Control Plan 2

## Changing the Scheduled Control Plan

### About Changing the Scheduled Control Plan by Using PI

Use the ACSSNM=CHG PI command to change or add the control plan that is scheduled for a customer service number. You can schedule a future date when the control plan will become active for the service number. Otherwise the control plan is activated immediately for the service number. For example, the following PI command schedules the Postpaid control plan for the 012234787 service number for the Telco customer:

```
ACSSNM=CHG:CUSTOMER=Telco,SERVICE_NUMBER=012234787,CONTROLPLAN=Postpaid,SCHE
DULE_DATE=20130901080000;
```

After successfully updating the control plan scheduled to a customer service number, the PI returns this message:

```
ACSSNM=CHG:ACK;
```

If unsuccessful, then the PI may return any of the following error codes: 101, 102, 103, 108, 118, 141, 143, 144, or 145.

### Required Parameters

Here are the required parameters for this command.

#### CUSTOMER

**Syntax:** CUSTOMER=*name*  
**Description:** The name of an existing customer.  
**Type:** String  
**Optionality:** Required  
**Allowed:** A string of up to 50 characters.  
**Example:** CUSTOMER=Customer A

#### SERVICE\_NUMBER

**Syntax:** SERVICE\_NUMBER=*string*  
**Description:** The service number for which you want to add or change the scheduled control plan.  
**Type:** String  
**Optionality:** Required  
**Allowed:** A string of up to 32 characters. Valid characters are 0–9, A–F, \*, #.  
**Example:** SERVICE\_NUMBER=012234787

#### CONTROLPLAN

**Syntax:** CONTROLPLAN=*string*  
**Description:** The name of an existing control plan that the service number will use.  
**Type:** String  
**Optionality:** Required  
**Allowed:** A string of up to 50 characters  
**Example:** CONTROLPLAN=Control Plan 2

### Optional Parameter

The ACSSNM=CHG PI command accepts the following optional parameter.

## SCHEDULE\_DATE

<b>Syntax:</b>	SCHEDULE_DATE= <i>date</i>
<b>Description:</b>	The date when the control plan will be activated for the service number. Specify a date in the following format: YYYYMMDDHHmmSS.
<b>Type:</b>	String
<b>Optionality:</b>	Optional
<b>Notes:</b>	To activate the control plan immediately for the service number, do not specify a schedule date.
<b>Example:</b>	SCHEDULE_DATE=20130901080000

## Querying Customer Service Numbers

### About Querying Customer Service Numbers by Using PI

Use the ACSSNM=QRY PI command to query the database for the details of the service numbers allocated to a specified ACS customer. After successfully performing a service number query, the PI returns this message:

```
ACSSNM=QRY:ACK:
  CUSTOMER=name, SERVICE_NUMBER=n[,SERVICE_NUMBER=n][, ...]
```

Where:

- *name* is the name of the customer.
- *n* is a service number allocated to the customer.

If unsuccessful, then the PI may return either of the following error codes: 118 or 140.

### Required Parameter

Here is the required parameter for this command.

## CUSTOMER

<b>Syntax:</b>	CUSTOMER= <i>name</i>
<b>Description:</b>	The name of an existing customer.
<b>Type:</b>	String
<b>Optionality:</b>	Required
<b>Allowed:</b>	A string of up to 50 characters.
<b>Example:</b>	CUSTOMER=Customer A

## Deleting Customer Service Numbers

### About Deleting Customer Service Numbers by Using PI

Use the ACSSNM=DEL PI command to delete a service number for a specified ACS customer. After successfully deleting a service number, the PI returns this message:

```
ACSSNM=DEL:ACK;
```

If unsuccessful, then the PI may return either of the following error codes: 118 or 140.

## Required Parameters

Here are the required parameters for this command.

CUSTOMER

**Syntax:** CUSTOMER=*name*  
**Description:** The name of an existing customer.  
**Type:** String  
**Optionality:** Required  
**Allowed:** A string of up to 50 characters.  
**Example:** CUSTOMER=Customer A

SERVICE\_NUMBER

**Syntax:** SERVICE\_NUMBER=*string*  
**Description:** The service number to add or delete.  
**Type:** String  
**Optionality:** Required  
**Allowed:** A string of up to 32 characters. Valid characters are 0–9, A–F, \*, #.  
**Example:** SERVICE\_NUMBER=115

## Adding Customer Termination Numbers

### About Adding Customer Termination Numbers by Using PI

Use the PI ACSTNM=ADD command to add termination numbers for a specified ACS customer.

To add a single termination number for a customer specify, only the *CUSTOMER* (on page 6) and *PREFIX* (on page 19) parameters.

To add a range of termination numbers for a customer, specify all the parameters. You specify the range by using a combination of the *PREFIX*, *MIN\_LENGTH* (on page 19) and *MAX\_LENGTH* (on page 19) parameters. For example, you could specify the following range:

```
PREFIX=01473, MIN_LENGTH=6, MAX_LENGTH=10  
The resulting termination number range would be: 01473XXXXY
```

Where *X* is a digit that must be present in the termination number, and *Y* is a digit that may be present up to *MAX\_LENGTH*.

After successfully adding termination numbers for a customer, the PI returns this message:

```
ACSTNM=ADD:ACK;
```

If unsuccessful, then the termination numbers are not added and the PI may return any of the following error codes: 118, 130, 131, 132, 133, 139, or 140.

## Required Parameters

Here are the required parameters for this command.

CUSTOMER

**Syntax:** CUSTOMER=*name*  
**Description:** The name of an existing customer.  
**Type:** String  
**Optionality:** Required



**Allowed:** A string of up to 50 characters.

**Example:** CUSTOMER=Customer A

PREFIX

**Syntax:** PREFIX=*string*

**Description:** The termination number prefix to add or delete.

**Type:** String

**Optionality:** Required.

**Allowed:** A string of up to 32 characters. Valid characters are 0–9, A–F, \*, #.

**Example:** PREFIX=0179

## Optional Parameters

ACSTNM=ADD accepts the following optional parameters.

MIN\_LENGTH

**Syntax:** MIN\_LENGTH=*integer*

**Description:** The minimum length for the termination number.

**Type:** Integer

**Optionality:** Optional (default used if not set).

**Allowed:** A value that is not less than the PREFIX length and not greater than 32.

**Default:** PREFIX length

**Example:** MIN\_LENGTH=4

MIN\_LENGTH

**Syntax:** MAX\_LENGTH=*integer*

**Description:** The maximum length for the termination number.

**Type:** Integer

**Optionality:** Optional (default used if not set).

**Allowed:** A value that is not less than MIN\_LENGTH and not greater than 32.

**Default:** PREFIX length plus one (1), or 32 if the PREFIX length is 32.

**Example:** MAX\_LENGTH=10

## Querying Customer Termination Numbers

### About Querying Customer Termination Numbers by Using PI

Use the ACSTNM=QRY PI command to query the database for the details of the termination numbers assigned to a specified ACS customer. After successfully performing a termination number query, the PI returns this message:

```
ACSTNM=QRY:ACK:
  CUSTOMER=name, TERMINATION_NUMBER=n[,TERMINATION_NUMBER=n[, ... ]]
```

Where:

- *name* is the name of the customer.
- *n* is a valid termination number for the customer.

If unsuccessful, then the PI may return the following error codes: 118 or 140.

### Required Parameters

Here are the required parameters for this command.

CUSTOMER

**Syntax:** CUSTOMER=*name*  
**Description:** The name of an existing customer.  
**Type:** String  
**Optionality:** Required  
**Allowed:** A string of up to 50 characters.  
**Example:** CUSTOMER=Customer A

PREFIX

**Syntax:** PREFIX=*string*  
**Description:** The termination number prefix to add or delete.  
**Type:** String  
**Optionality:** Required.  
**Allowed:** A string of up to 32 characters. Valid characters are 0–9, A–F, \*, #.  
**Example:** PREFIX=0179

## Deleting Customer Termination Numbers

### About Deleting Customer Termination Numbers by Using PI

Use the ACSTNM=DEL PI command to delete a termination number prefix for a specified ACS customer. After successfully deleting a termination number prefix, the PI returns this message:

```
ACSTNM=DEL:ACK;
```

If unsuccessful, then the PI may return any of the following error codes: 118, 134, or 140.

### Required Parameter

Here is the required parameter for this command.

CUSTOMER

**Syntax:** CUSTOMER=*name*  
**Description:** The name of an existing customer.  
**Type:** String  
**Optionality:** Required  
**Allowed:** A string of up to 50 characters.  
**Example:** CUSTOMER=Customer A

## Managing FCI Data by Using PI

### About Managing FCI Data by Using PI

Use the ACSPFL=CHG PI command to update the furnish charging information (FCI) data held in the following profile tags in the ACS service number profile block:

- FCI Country Code
- FCI On
- FCI Service Code

For more information about using ACSPFL=CHG, see *Changing a Profile Entry* (on page 10).

Use the ACSPFL=QRY PI command to query the FCI data for a customer. For more information, see *Querying a Profile Entry* (on page 13).

For more information about profile blocks and profile tags, see the discussion on the main components of ACS in *ACS Technical Guide*.



# Error Code Lists

## Overview

### Introduction

This chapter explains the error codes for Oracle Communications Convergent Charging Controller provisioning interface (PI) commands.

### In this chapter

---

This chapter contains the following topics.

PI Chassis Errors.....	23
PI Command Errors.....	24

## PI Chassis Errors

### Format

NACK:*Code-Message*;

**Example:** ACSCLI=QRY:NACK:70-TOO MANY SESSIONS

### Error List

This table describes the PI Chassis error codes.

Code	Message	Description
70	TOO MANY SESSIONS	All PI sessions are in use.
71	LOGON SYNTAX ERROR	The login string was incorrectly formatted.
72	INVALID LOGON - username, password	Invalid username and/or password
73	INVALID LOGON - user not allowed on this port	The user attempted to log in to the wrong PI port.
74	INVALID LOGON - host	The PI client is unknown.
75	UNKNOWN COMMAND	Client sent an unknown command.
76	USER DOES NOT HAVE SUFFICIENT SECURITY	The user's security level is less than the command's security level.
77	SYNSTAMP NOT FOUND	Synstamps are turned on, but the client did not send one.
78	SYNSTAMP NOT VALID	Synstamps are turned on, but the synstamp sent by the client is invalid.

Code	Message	Description
79	INVALID OR MISSING CHECKSUM	Checksums are turned on, but the client is one of the following: <ul style="list-style-type: none"> <li>• Did not send one</li> <li>• It was invalid</li> </ul>
80	UNKNOWN PARAMETER FOR COMMAND	A parameter was sent that was not valid for this command.
81	MISSING PARAMETERS FROM COMMAND	A required parameter is missing.
82		Undefined
83	DUPLICATE PARAMETER	The client sent two identically named parameters.
84	ERROR RUNNING PROCEDURE	An internal error occurred running the command.
85	USER SESSION TERMINATED	The user's session has been terminated by an administrator.
86	COMMAND TOO BIG	The command sent is too long. Indicates an incorrectly formatted command.
87	COMMAND SYNTAX ERROR	The command sent is incorrectly formatted.
88	PARAMETER NAME TOO BIG	A parameter name is too long. Indicates the command was incorrectly formatted.
89	PARAMETER VALUE TOO BIG	A parameter value is too long. Indicates the command was incorrectly formatted.
90	SYNSTAMP OUT OF PLACE	The synstamp is not at the end of the command, but before the checksum.
91	TIMEOUT	The command took too long to run.

## PI Command Errors

### Format

*Command*:NACK:*Code*-*Message*:*value*;

Where:

- *Command* is the PI command
- *Code* is the PI error code
- *Message* is the PI error message and can contain any characters except semi-colon
- In the message, *value* will be replaced with a suitable value by the command.

**Example:** ACSCLI=QRY:NACK:104-CLI does not exist:912233445566

### Error List

This table lists the error codes and error code descriptions for the PI commands listed in the ACS PI command list.

Code	Message	Commands
101	<i>text</i> Where the <i>text</i> contains the details of the error. This error is used to report any other errors that are not defined below.	All commands

Code	Message	Commands
102	Badly formatted parameter <i>parameter</i> Where <i>parameter</i> is the name of the parameter causing the error.	All commands
103	CALLPLAN does not exist <i>control_plan</i> Where <i>control_plan</i> is the name of an invalid control plan.	ACSCLI=ADD ACSCPL=EXP ACSCPL=DEL ACSSNM=CHG
104	CLI does not exist <i>cli</i> Where <i>cli</i> is an invalid CLI number.	ACSCLI=DEL ACSCLI=QRY
105	No required parameters	All commands
106	Too many numbers in ALLOWED list	ACSCLI=ADD
107	Invalid action <i>action</i> Where <i>action</i> is an invalid command action.	All commands
108	SQL write error	ACSCLI=ADD ACSCLI=DEL ACSSNM=CHG
109	SQL read error	ACSCLI=ADD ACSCLI=DEL ACSCLI=QRY
110	Internal error encoding profile	ACSCLI=ADD ACSCLI=DEL ACSPFL=CHG
111	TABLE does not exist <i>table_name</i> Where <i>table_name</i> is an invalid database table name.	ACSPFL=CHG ACSPFL=QRY
112	ID_COLUMN does not exist <i>column_name</i> Where <i>column_name</i> is an invalid column name for the specified table.	ACSPFL=CHG ACSPFL=QRY
113	ID does not exist <i>id</i> Where <i>id</i> is invalid.	ACSPFL=CHG ACSPFL=QRY
114	PROFILE_COLUMN does not exist <i>column_name</i> Where <i>column_name</i> is an invalid column name for the profile.	ACSPFL=CHG ACSPFL=QRY
115	TAG does not exist <i>tag_name</i> Where <i>tag_name</i> is an invalid name for the specified profile tag.	ACSPFL=CHG ACSPFL=QRY
116	TYPE is not valid <i>type_name</i> Where <i>type_name</i> is an invalid profile type.	ACSPFL=CHG ACSPFL=QRY
117	VALUE is not valid <i>value</i> Where <i>value</i> is an invalid value for the specified profile tag.	ACSPFL=CHG ACSPFL=QRY

Code	Message	Commands
118	Customer does not exist <i>customer_name</i> Where <i>customer_name</i> is not a valid ACS customer.	ACSCST=QRY ACSCPL=EXP ACSCPL=IMP ACSCPL=DEL ACSSNM=ADD ACSSNM=CHG ACSSNM=QRY ACSSNM=DEL ACSTNM=ADD ACSTNM=QRY ACSTNM=DEL
120	FILENAME does not exist <i>file_name</i>	ACSCPL=IMP
121	FILENAME has insufficient permissions <i>file_name</i>	ACSCPL=IMP
130	Invalid termination prefix	ACSTNM=ADD
131	Invalid minimum termination length	ACSTNM=ADD
132	Invalid maximum termination length	ACSTNM=ADD
133	Overlapping termination ranges not allowed	ACSTNM=ADD
134	Termination number or range does not exist	ACSTNM=DEL
135	Service number not found for customer	ACSSNM=DEL
136	Parent customer not found	ACSCST=ADD
137	Reseller cannot have a parent customer	ACSCST=ADD
138	Reseller cannot have a parent customer	ACSCST=ADD
139	Minimum termination number length greater than maximum termination number length	ACSTNM=ADD
140	Duplicate service numbers not allowed	ACSCST=ADD ACSSNM=ADD ACSSNM=QRY ACSSNM=DEL ACSTNM=ADD ACSTNM=QRY ACSTNM=DEL
141	Parameter too long	ACSSNM=CHG
142	Customer already exists	ACSCST=ADD
143	Invalid service number	ACSSNM=ADD ACSSNM=CHG
144	Invalid customer name	ACST=ADD ACSPL=IMP ACSPL=EXP ACSPL=DEL
145	Parameter too short	ACSSNM=CHG
146	Invalid date	ACSSNM=CHG







# Glossary of Terms

## ACS

Advanced Control Services configuration platform.

## ANI

Automatic Number Identification - Term used in the USA by long-distance carriers for CLI.

## CCS

- 1) Charging Control Services component.
- 2) Common Channel Signalling. A signalling system used in telephone networks that separates signalling information from user data.

## CLI

Calling Line Identification - the telephone number of the caller. Also referred to as ANI.

## Convergent

Also “convergent billing”. Describes the scenario where post-paid and pre-paid calls are handed by the same service platform and the same billing system. Under strict converged billing, post-paid subscribers are essentially treated as “limited credit pre-paid”.

## DTMF

Dual Tone Multi-Frequency - system used by touch tone telephones where one high and one low frequency, or tone, is assigned to each touch tone button on the phone.

## FCI

Furnish Charging Information. An INAP operation sent from ACS to the SSP to control the contents of EDRs produced by the SSP.

## GUI

Graphical User Interface

## IN

Intelligent Network

## INAP

Intelligent Network Application Part - a protocol offering real time communication between IN elements.

## IP

- 1) Internet Protocol
- 2) Intelligent Peripheral - This is a node in an Intelligent Network containing a Specialized Resource Function (SRF).

## **MIN**

Mobile Identification Number, also known as an MSID.

## **MSID**

Mobile Subscriber Identification, also known as an MIN.

## **PI**

Provisioning Interface - used for bulk database updates/configuration instead of GUI based configuration.

## **SLC**

Service Logic Controller (formerly UAS).

## **SMS**

Depending on context, can be:

- Service Management System hardware platform
- Short Message Service
- Service Management System platform
- Convergent Charging Controller Service Management System application

## **SQL**

Structured Query Language is a database query language.

## **SRF**

Specialized Resource Function – This is a node on an IN which can connect to both the SSP and the SLC and delivers additional special resources into the call, mostly related to voice data, for example play voice announcements or collect DTMF tones from the user. Can be present on an SSP or an Intelligent Peripheral (IP).

## **SSP**

Service Switching Point

## **TCP**

Transmission Control Protocol. This is a reliable octet streaming protocol used by the majority of applications on the Internet. It provides a connection-oriented, full-duplex, point to point service between hosts.

## **Telco**

Telecommunications Provider. This is the company that provides the telephone service to customers.

## **Telecommunications Provider**

See Telco.

# Index

## A

- About Adding a CLI to ACS Numbers by Using PI • 3
- About Adding an ACS Customer by Using PI • 8
- About Adding Customer Service Numbers by Using PI • 15
- About Adding Customer Termination Numbers by Using PI • 18
- About Changing a Profile Entry by Using PI • 10
- About Changing the Scheduled Control Plan by Using PI • 16
- About Deleting a CLI in ACS Numbers by Using PI • 4
- About Deleting a Control Plan by Using PI • 7
- About Deleting Customer Service Numbers by Using PI • 17
- About Deleting Customer Termination Numbers by Using PI • 20
- About Exporting a Control Plan by Using PI • 5
- About Importing a Control Plan by Using PI • 6
- About Managing FCI Data by Using PI • 21
- About Querying a CLI in ACS Numbers by Using PI • 5
- About Querying a Profile Entry by Using PI • 13
- About Querying an ACS Customer by Using PI • 10
- About Querying Customer Service Numbers by Using PI • 17
- About Querying Customer Termination Numbers by Using PI • 19
- About Service Provider Restrictions • 2, 8
- About This Document • v
- ACS • 29
- ACS PI Command List • 1
- Adding a CLI to ACS Numbers by Using PI • 3
- Adding an ACS Customer • 8
- Adding Customer Service Numbers • 15
- Adding Customer Termination Numbers • 18
- ALLOWED • 4, 5
- ANI • 29
- Audience • v

## C

- CALLPLAN • 4, 6, 7, 8
- CCS • 29
- Changing a Profile Entry • 10, 21
- Changing the Scheduled Control Plan • 16
- CLI • 4, 5, 29
- Command List • 1
- CONTROLPLAN • 15, 16
- Convergent • 29
- Copyright • ii
- CUSTOMER • 6, 7, 8, 10, 15, 16, 17, 18, 20
- CUSTOMER\_REFERENCE • 9

## D

- Deleting a CLI From ACS Numbers • 4
- Deleting a Control Plan • 7
- Deleting Customer Service Numbers • 17
- Deleting Customer Termination Numbers • 20
- DESCRIPTION • 9
- Document Conventions • vi
- DTMF • 29

## E

- Error Code Lists • 23
- Error List • 23, 24
- Exporting a Control Plan • 5

## F

- FCI • 29
- FILENAME • 7
- Format • 23, 24

## G

- GUI • 29

## I

- ID • 11, 13
- ID\_COL • 12, 14
- Importing a Control Plan • 6
- IN • 29
- INAP • 29
- IP • 29

## M

- Managing FCI Data by Using PI • 21
- MIN • 30
- MIN\_LENGTH • 18, 19
- MSID • 30

## O

- Optional Parameter • 15, 16
- Optional Parameters • 4, 9, 11, 13, 19
- Overview • 1, 3, 23

## P

- PARENT • 9
- PI • 30
- PI Chassis Errors • 23
- PI Command Errors • 24
- PI Commands Overview • 1
- piAcsSms Package • 3
- PREFIX • 18, 19, 20
- Prerequisites • v
- PROFILE\_COL • 11, 13

## Q

- Querying a CLI in ACS Numbers • 5
- Querying a Profile Entry • 13, 21

Querying an ACS Customer • 10  
Querying Customer Service Numbers • 17  
Querying Customer Termination Numbers • 19

## **R**

Related Documents • v  
Required Parameter • 5, 10, 17, 20  
Required Parameters • 4, 6, 7, 8, 11, 13, 15, 16,  
18, 20  
RESELLER\_FLAG • 10

## **S**

SCHEDULE\_DATE • 17  
Scope • v  
SERVICE\_NUMBER • 15, 16, 18  
SLC • 30  
SMS • 30  
SQL • 30  
SRF • 30  
SSP • 30

## **T**

TABLE • 11, 13  
TAG • 11, 14  
TCP • 30  
Telco • 30  
TELCO\_MANAGED • 9  
Telecommunications Provider • 30  
TYPE • 12, 14  
Typographical Conventions • vi

## **V**

VALUE • 12