Oracle® Service Architecture Leveraging Tuxedo (SALT) Reference Guide





Oracle Service Architecture Leveraging Tuxedo (SALT) Reference Guide, Release 22c

G11833-01

Copyright © 1996, 2025, Oracle and/or its affiliates.

Primary Author: Priya Pathak

Contributing Authors: Tulika Das

Contributors: Maggie.Li

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software, software documentation, data (as defined in the Federal Acquisition Regulation), or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs) and Oracle computer documentation or other Oracle data delivered to or accessed by U.S. Government end users are "commercial computer software," "commercial computer software documentation," or "limited rights data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, reproduction, duplication, release, display, disclosure, modification, preparation of derivative works, and/or adaptation of i) Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs), ii) Oracle computer documentation and/or iii) other Oracle data, is subject to the rights and limitations specified in the license contained in the applicable contract. The terms governing the U.S. Government's use of Oracle cloud services are defined by the applicable contract for such services. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle®, Java, MySQL, and NetSuite are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Inside are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Epyc, and the AMD logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

Contents

1 SALT Command Reference

1.1	GWV	VS(5)	1
	1.1.1	Name	2
	1.1.2	Synopsis	2
	1.1.3	Description	2
	1.1.4	Environment Variables	3
	1.1.5	Deprecation	3
	1.1.6	Diagnostics	3
	1.1.7	Examples	3
1.2	jsono	evt(1)	4
	1.2.1	Name	4
	1.2.2	Synopsis	4
	1.2.3	Description	4
	1.2.4	Parameters/Options	5
	1.2.5	Diagnostics	5
	1.2.6	Environment Variables	5
	1.2.7	Examples	5
	1.2	7.7.1 Input/Output	5
	1.2	2.7.2 Running the Command	6
	1.2	2.7.3 Results	6
1.3	tmsc	d(1)	8
	1.3.1	Name	8
	1.3.2	Synopsis	8
	1.3.3	Description	8
	1.3.4	Parameters and Options	8
	1.3.5	Example(s)	9
	1.3.6	Diagnostics	9
1.4	tmws	sdlgen	10
	1.4.1	Name	10
	1.4.2	Synopsis	10
	1.4.3	Description	10
	1.4.4	Deprecation	11
	1.4.5	Diagnostics	12

1.4.6	Example(s)	12
1.5 wsa	dmin	12
1.5.1	Name	13
1.5.2	Synopsis	13
1.5.3	Description	13
1.5.4	Example(s)	18
1.6 wsc	obolcvt	19
1.6.1	Name	19
1.6.2	Synopsis	19
1.6.3	Description	19
1.6.4	Parameters	19
1.6.5	Examples	20
1.7 wsd	lcvt	21
1.7.1	Name	21
1.7.2	Synopsis	21
1.7.3	Description	21
1.7.4	Parameters	21
1.7.5	Environment Variable(s)	23
1.7.6	Diagnostics	23
1.7.7	Example(s)	23
1.8 wslc	padcf	23
1.8.1	Name	24
1.8.2	Synopsis	24
1.8.3	Description	24
1.8.4	Environment Variables	25
1.8.5	Diagnostics	25
1.9 wsu	nloadcf	25
1.9.1	Name	25
1.9.2	Synopsis	25
1.9.3	Description	25
1.9.4	Environment Variables	25
SALT V	Veb Service Definition File Reference	
2.1 Ove	rview	1
2.2 SAL	T WSDF Format	1
2.3 XML	_ Schema	2
2.4 SAL	T WSDF Examples	2
2.5 SAL	T WSDF Element Descriptions	4
2.5.1	<definition></definition>	4
2.5.2	<wsbinding></wsbinding>	5
2.5.3	<servicegroup></servicegroup>	6

2

	<service></service>	6
2.5.5	<input/>	7
2.5.6	<output></output>	8
2.5.7	<fault></fault>	8
2.5.8	<msghandler></msghandler>	9
2.5.9	<policy></policy>	9
2.5.10	<property></property>	11
2.5.11	<soap></soap>	12
2.5.12	<accessingpoints></accessingpoints>	13
2.5.13	<endpoint></endpoint>	13
2.5.14	<realm></realm>	14
SALT De	eployment File Reference	
3.1 Overv		1
	SALTDEPLOY Format	1
	Schema	2
	SALT SALTDEPLOY Example	3
3.3.2	SALT SALTDEPLOY Element Descriptions	3
3.3.3	<deployment></deployment>	3
3.3.	.3.1 <wsdf></wsdf>	4
2.2	.3.2 <wsgateway></wsgateway>	4
3.3.		·
	.3.3 <system></system>	12
3.3.	.3.3 <system> S-AT Assertion Reference</system>	
3.3.	S-AT Assertion Reference	
3.3. SALT W: 4.1 Overv	S-AT Assertion Reference	12
3.3. SALT W: 4.1 Overv	S-AT Assertion Reference	
3.3. SALT W 4.1 Overv 4.2 Policy	S-AT Assertion Reference	12 1 1
3.3. SALT W 4.1 Overv 4.2 Policy SALT W 5.1 Overv	S-AT Assertion Reference view y File Example S-ReliableMessaging Policy Assertion Reference	12 1 1 1
3.3. SALT W 4.1 Overv 4.2 Policy SALT W 5.1 Overv 5.2 WS-R	S-AT Assertion Reference view y File Example S-ReliableMessaging Policy Assertion Reference view RM Policy Assertion Format	12 1 1 1 1
3.3. SALT W: 4.1 Overv 4.2 Policy SALT W: 5.1 Overv 5.2 WS-R 5.3 WS-R	S-AT Assertion Reference view y File Example S-ReliableMessaging Policy Assertion Reference view RM Policy Assertion Format RM Assertion File Example	12 1 1 1 1 1 1 2
3.3. SALT W: 4.1 Overv 4.2 Policy SALT W: 5.1 Overv 5.2 WS-R 5.3 WS-R	S-AT Assertion Reference view y File Example S-ReliableMessaging Policy Assertion Reference view RM Policy Assertion Format	12 1 1 1 1
3.3. SALT W: 4.1 Overv 4.2 Policy SALT W: 5.1 Overv 5.2 WS-R 5.3 WS-R 5.4 WS-R	S-AT Assertion Reference view y File Example S-ReliableMessaging Policy Assertion Reference view RM Policy Assertion Format RM Assertion File Example	12 1 1 1 1 1 1 2
3.3. SALT W: 4.1 Overv 4.2 Policy SALT W: 5.1 Overv 5.2 WS-R 5.3 WS-R 5.4 WS-R 5.4.1	S-AT Assertion Reference view y File Example S-ReliableMessaging Policy Assertion Reference view RM Policy Assertion Format RM Assertion File Example RM Assertion Element Description	12 1 1 1 1 1 1 2 2
3.3. SALT W: 4.1 Overv 4.2 Policy SALT W: 5.1 Overv 5.2 WS-R 5.3 WS-R 5.4 WS-R 5.4.1 5.4.2	S-AT Assertion Reference view y File Example S-ReliableMessaging Policy Assertion Reference view RM Policy Assertion Format RM Assertion File Example RM Assertion Element Description <wsrm:inactivitytimeout></wsrm:inactivitytimeout>	12 1 1 1 1 1 2 2 2 3
3.3. SALT W: 4.1 Overv 4.2 Policy SALT W: 5.1 Overv 5.2 WS-R 5.3 WS-R 5.4 WS-R 5.4.1 5.4.2 5.4.3	S-AT Assertion Reference view y File Example S-ReliableMessaging Policy Assertion Reference view RM Policy Assertion Format RM Assertion File Example RM Assertion Element Description <wsrm:inactivitytimeout> <wsrm:acknowledgmentinterval></wsrm:acknowledgmentinterval></wsrm:inactivitytimeout>	12 1 1 1 1 1 1 2 2 2 3 3
3.3. SALT W: 4.1 Overv 4.2 Policy SALT W: 5.1 Overv 5.2 WS-R 5.3 WS-R 5.4 WS-R 5.4.1 5.4.2 5.4.3 5.4.4	S-AT Assertion Reference view y File Example S-ReliableMessaging Policy Assertion Reference view RM Policy Assertion Format RM Assertion File Example RM Assertion Element Description <wsrm:inactivitytimeout> <wsrm:acknowledgmentinterval> <wsrm:baseretransmissioninterval></wsrm:baseretransmissioninterval></wsrm:acknowledgmentinterval></wsrm:inactivitytimeout>	12 1 1 1 1 2 2 2 3 3 3

6 SALT WS-SecurityPolicy Assertion 1.2 Reference
--

6.1 Ove	5.1 Overview			
6.2 SA	5.2 SALT WSSP 1.2 Policy File Examples			
6.2.1	WSSP 1.2 Policy File Sample	2		
6.2.2	Wssp1.2-Wss1.0-X509.xml File Sample	3		
6.3 SA	LT WSSP 1.2 Policy Templates	3		
6.4 SA	LT WSSP1.2 Assertion Description	4		
6.4.1	<sp:signedparts></sp:signedparts>	4		
6	4.1.1 Limitations	4		
6.4.2	<sp:usernametoken></sp:usernametoken>	4		
6	4.2.1 Limitations	4		
6.4.3	<sp:x509token></sp:x509token>	5		
6	4.3.1 Limitations	5		
6.4.4	<sp:algorithmsuite></sp:algorithmsuite>	5		
6	4.4.1 Limitations	5		
6.4.5	<sp:layout></sp:layout>	5		
6	5.4.5.1 Limitations	6		
6.4.6	<sp:transportbinding></sp:transportbinding>	6		
6	.4.6.1 Limitations	6		
6.4.7	<sp:asymmetricbinding></sp:asymmetricbinding>	7		
6	.4.7.1 Limitations	7		
6.4.8	<sp:supportingtoken></sp:supportingtoken>	8		
6	4.8.1 Limitations	8		
SALT	WS-SecurityPolicy Assertion 1.0 Reference			
	•			
	erview	1		
7.2 SA	LT WSSP 1.0 Policy Assertion Format	1		
7.3 SA	LT WSSP 1.0 Assertion File Example	2		
7.4 SA	LT WSSP 1.0 Policy Templates	3		
7.5 SA	LT WSSP 1.0 Assertion Element Description	3		
7.5.1	<canonicalizationalgorithm></canonicalizationalgorithm>	4		
7.5.2	<claims></claims>	4		
7.5.3	<digestalgorithm></digestalgorithm>	4		
7.5.4	<identity></identity>	4		
7.5.5	<integrity></integrity>	5		
7.5.6	<messageparts></messageparts>	5		
7.5.7	<securitytoken></securitytoken>	5		
7.5.8	<signaturealgorithm></signaturealgorithm>	6		

7

7.5.9	<supported tokens=""></supported>	/
7.5.10	<target></target>	7
7.5.11	<transform></transform>	8
7.5.12	<usepassword></usepassword>	8
7.5.13	Usage of MessageParts	10
7.5	5.13.1 Pre-Defined Message Part Selection Function	10

List of Examples

1-1	CMANS Description in the LIBECONFIC File	2
	GWWS Description in the UBBCONFIG File	<u>3</u>
1-2	<u>Input</u>	<u>6</u>
1-3	<u>Output</u>	<u>6</u>
1-4	Running the command	<u>6</u>
1-5	<u>MIF</u>	<u>6</u>
1-6	fml32 Table	<u>7</u>
1-7	SALT Deploy Definition	<u>7</u>
1-8	svcfile Content	<u>9</u>
1-9	COBOL copybook record	<u>20</u>
2-1	Native WSDF (Composed Manually)	<u>3</u>
2-2	Non-Native WSDF (Generated from an External WSDL Document)	<u>3</u>
3-1	SALT SALTDEPLOY File	<u>3</u>
4-1	policy.xml File with an ATAssertion Element	<u>1</u>
5-1	Sample WS-ReliableMessaging Policy Assertion File	<u>2</u>
6-1	WSSP 1.2 Policy File Sample	<u>2</u>
6-2	Wssp1.2-Wss1.0-X509.xml File Sample	<u>3</u>
6-3	Supported TransportToken Assertions	<u>6</u>
6-4	Supported AsymmetricBinding Assertion	<u>7</u>
6-5	Supported SupportingToken Assertion	<u>9</u>
7-1	WSSP 1.0 Policy File Sample	<u>2</u>
7-2	wsp:Body() Function	<u>11</u>

List of Figures

2-1	SALT Web Service Definition File Format:	2
3-1	SALT Deployment File Format	2
5-1	WS-ReliableMessaging Policy Assertion Formating	2
7-1	SALT Supported WS-SecurityPolicy 1.0 Assertion Format	2

List of Tables

1-1	SALT Commands and Functions	<u>1</u>
1-2	wsdlcvt-Created File Suffixes	<u>22</u>
2-1	<u>Definition Attributes</u>	<u>4</u>
2-2	WSBinding Attributes	<u>5</u>
2-3	<servicegroup> Attributes</servicegroup>	<u>6</u>
2-4	Input Attributes	7
2-5	Output Attributes	<u>8</u>
2-6	Fault Attributes	<u>9</u>
2-7	Policy Attributes	<u>10</u>
2-8	Property Attributes	<u>11</u>
2-9	<property> Name List</property>	<u>12</u>
2-10	Property headerMapping	<u>12</u>
2-11	SOAP Attributes	<u>12</u>
2-12	Endpoint Attributes	<u>13</u>
3-1	<u>ImportAttributes</u>	<u>4</u>
3-2	GWInstance Attributes	<u>4</u>
3-3	Network Attributes	<u>5</u>
3-4	Service Attributes	<u>6</u>
3-5	Service Attributes	<u>6</u>
3-6	Binding Attributes	7
3-7	Ipv4 and IPv6 Address Formats	<u>8</u>
3-8	Endpoint Attributes	<u>8</u>
3-9	WSAddressing Attributes	<u>9</u>
3-10	Endpoint Attributes	<u>9</u>
3-11	Service Attributes	<u>9</u>
3-12	Properties Attributes	<u>10</u>
3-13	GWWS Property Attributes	<u>10</u>
3-14	GWWS Property List	<u>11</u>
3-15	Interface Attributes	<u>14</u>
6-1	WSSP 1.2 Policy Template Files	<u>3</u>
7-1	SALT WSSP 1.0 Policy Template Files	<u>3</u>
7-2	CanonicalizationAlgorithm Attribute	<u>4</u>
7-3	DigestAlgorithm Attributes	<u>4</u>
7-4	Integrity Attributes	<u>5</u>
7-5	MessageParts Attributes	<u>5</u>
7-6	SecurityToken Attributes	<u>6</u>

7-7	SignatureAlgorithm Attributes	7
7-8	Transform Attributes	<u>8</u>
7-9	UsePassword Attributes	<u>c</u>
7-10	SALT Supported Message Part Selection Function	<u>10</u>

SALT Command Reference

The SALT Command Reference describes system processes and commands delivered with the SALT software.

The following table lists SALT commands and functions:

Table 1-1 SALT Commands and Functions

Name	Description
Name	Description
<u>GWWS(5)</u>	Web service gateway server.
jsoncvt(1)	JSON object to service metadata converter.
tmscd(1)	Command line utility used to activate and deactivate service contract discovery.
tmwsdlgen	WSDL document generator.
wsadmin	SALT administration command interpreter.
wscobolcvt	Generates SALT artifacts from COBOL copybook for exposing COBOL service as a web service.
<u>wsdlcvt</u>	WSDL document converter.
<u>tmwsdlgen</u>	Reads SALT Deployment file and other referenced artifacts. Loads a binary SALTCONFIG file.
wsunloadcf	Reads a binary SALTCONFIG file, creates a SALT deployment file and other referenced files (WSDF files, WS-Policy files).

- GWWS(5)
- jsoncvt(1)
- <u>tmscd(1)</u>
- <u>tmwsdlgen</u>
- wsadmin
- wscobolcvt
- wsdlcvt
- wsloadcf
- wsunloadcf

1.1 GWWS(5)

The section contains the following topics:

- Name
- Synopsis
- <u>Description</u>
- Environment Variables



- Deprecation
- Diagnostics
- Examples

1.1.1 Name

GWWS - Web service gateway server.

1.1.2 Synopsis

```
GWWS SRVGRP="identifier" SRVID=number [other_parms]
CLOPT="-A -- -i InstanceID [-a <scheme>://<host>:<port>]"
```

1.1.3 Description

The GWWS server is the Web service gateway for Tuxedo applications, the core component of SALT. The GWWS gateway server provides communication with Web service programs via SOAP 1.1/1.2 protocols and RESTful protocols. The GWWS server has bi-directional (inbound/outbound) capability. It can accept SOAP and RESTful requests from Web service applications and pass Tuxedo native calls to Tuxedo services (inbound). It also accepts Tuxedo ATMI requests and passes SOAP or RESTful calls to Web service applications (outbound). GWWS servers are used as Tuxedo system processes and are described in the *SERVERS section of the UBBCONFIG(5) file.

The CLOPT option is a string of command-line options passed to the GWWS server when it is booted. The GWWS server accepts the following CLOPT options:

-i InstanceID

Specifies the GWWS instance unique ID. It is used to distinguish multiple GWWS instances provided in the same Tuxedo domain. This value *must* be unique among multiple GWWS items within the UBBCONFIG file.



The InstanceID value must be pre-defined in the <WSGateway> section of the SALT Deployment File.

-a <scheme>://<host>:<port>

Web administration is disabled by default. In order to enable admin capabilities, the GWWS server must be configured in the UBBCONFIG file using the -a option as follows:

-a <scheme>://<host>:<port>.



Use the following URL to access the Web Admin Console:

<scheme>://<host>:<port>/admin



<scheme>

Can be 'http' or 'https'. If using 'https', GWWS must be configured for SSL capabilities by adding private-key and certificates in the same manner as securing application Web Services with SSL.

<host>

The name or IP address of the admin URL listening endpoint.

<port>

The port value of the admin URL listening endpoint.

1.1.4 Environment Variables

The SALTCONFIG environment variable must be set before the GWWS server is booted. Accesslog(5) can be enabled by setting environment variable TMENABLEALOG=y.



Note

Windows platforms: Add %TUXDIR%\bin\ssllibs to PATH

1.1.5 Deprecation

The following SALT 1.1 GWWS parameter is deprecated in the current release.

-c Config file

Specifies the SALT 1.1 configuration file.



(i) Note

Starting with the SALT 2.0 release, the GWWS server loads the SALT configuration from the binary SALTCONFIG file instead of the XML-based configuration file. The configuration file is no longer a GWWS server input parameter. The SALTCONFIG file must be generated using wsloadcf before booting GWWS servers.

1.1.6 Diagnostics

For inbound call, if an error occurs during SOAP message processing, the error is logged. The error is also translated into appropriate SOAP fault and/or HTTP error status code and returned to the Web service client.

For outbound call, if an error occurs during processing, the error is logged. The error is also translated into appropriate Tuxedo system error code (tperrno) and returned to the Tuxedo client.

1.1.7 Examples

Following is the GWWS Description in the UBBCONFIG File:

Example 1-1 GWWS Description in the UBBCONFIG File

*SERVERS

GWWS SRVGRP=GROUP1 SRVID=10



```
CLOPT="-A -- -i GW1"

GWWS SRVGRP=GROUP1 SRVID=11

CLOPT="-A -- -i GW2"

GWWS SRVGRP=GROUP2 SRVID=20

CLOPT="-A -- -i GW3"
```

(i) See Also

UBBCONFIG(5)

tmwsdlgen

SALT Deployment File Reference

SALT Web Service Definition File Reference

1.2 jsoncvt(1)

- Name
- Synopsis
- <u>Description</u>
- Parameters/Options
- Diagnostics
- Environment Variables
- Examples

1.2.1 Name

jsoncvt – JSON object to service metadata converter.

1.2.2 Synopsis

```
jsconcvt [-f inout.json [-f inout2.json ...]] [-i input.json [-i
input2.json ...]] [-o output.json [-o output2.json ...]] -s servicename -
m(POST / GET / PUT / DELETE) -a serviceaddress
```

1.2.3 Description

The jsconcvt command generates service metadata from JSON content, which can be used to construct service interfaces for easier application development. The command also generates fml32 tables and SALT deployment service definitions.

It is possible to mention more than 1 of each input and output payload samples by either separating the file names with spaces and enclosing the list in double-quotes, or specifying "-i" or "-o" multiple times. The corresponding definitions are concatenated in the metadata and fml32. This is to accommodate services that may return or accept data in different formats.



Input and output are optional, although specifying neither is not accepted. The metadata and fml32 files are generated using the service name as the base name. For example, a switch of "-s service1" generates files with names "service1.mif" and "service1.fml32".

Note

jsoncvt does not support long double value.

1.2.4 Parameters/Options

-f

Sample input and output json content. -jsoncvt uses this to generate a metadata service structure for the data received and returned by this service.

-i

Sample input json content. -jsoncvt uses this to generate a metadata service structure for the data received by this service.

-0

Sample output json content - jsoncvt uses this to generate a metadata service structure for the data returned by this service.

-s

Name of the service generated. Specified in metadata and SALT deploy file.

-m

Method for the service. Can be one of the following: POST, GET, PUT, or DELETE.

-a

Address of the external service.

1.2.5 Diagnostics

Error, warning or information messages are output to standard output.

1.2.6 Environment Variables

The TUXDIR and LANG environment variables must be set correctly.

1.2.7 Examples

Given the following JSON examples:

- Input/Output
- Running the Command
- Results

1.2.7.1 Input/Output

Input and output file examples are shown in the following examples:



Example 1-2 Input

```
$ cat balance.json
{
    "account":5563909,
    "location":"US"
}
```

Example 1-3 Output

1.2.7.2 Running the Command

An example of running the command is shown in example:

Example 1-4 Running the command

```
$ jsoncvt -i balance.json -o result.json -s balance -m POST -a
http://bank.com:4434/online_banking
Files balance.mif, balance.fml32 and balance.dep generated.
Please add the generated service definition - balance.dep - to the SALT
deploy configuration file.
```

1.2.7.3 Results

The end results are shown in the following examples:

Example 1-5 MIF

```
service=balance
tuxservice=balance
export=y
servicetype=service
servicemode=webservice
inbuf=FML32
outbuf=FML32
param=account
```



```
access=in
type=long
param=location
access=in
type=string
param=account
access=out
type=long
param=location
access=out
type=string
param=accounts
access=out
type=fml32
    param=type
    access=out
    type=string
    param=currency
    access=out
    type=string
    param=balance
    access=out
    type=double
```

Example 1-6 fml32 Table

FML32 JSON Mapping Generated by jsoncvt

*base 30000 # Customize base number if necessary.

#name	rel-number	type	flags	comment
#				
account	1	long	-	param
location	2	string	-	param
options	3	string	-	param
accounts	4	fml32	-	structured parameter
type	5	string	-	param
currency	6	string	_	param

Example 1-7 SALT Deploy Definition

```
<service name=balance
    content-type="JSON" output-buffer="FML32"
    address="http://bank.com:4434/online_banking"/>
```



(i) See Also

Creating the Oracle Tuxedo Service Metadata Repository

field_tables(5)

SALT Web Service Definition File Reference

1.3 tmscd(1)

- Name
- Synopsis
- Description
- · Parameters and Options
- Example(s)
- Diagnostics

1.3.1 Name

tmscd(1) – Activates and deactivates service contract discovery.

1.3.2 Synopsis

tmscd start|stop|status [-e] [-f <file>][id1 [id2 [...]]]

1.3.3 Description

The tmscd command line utility is used to activate and deactivate service contract discovery.

1.3.4 Parameters and Options

tmscd accepts following parameters and options:

start|stop|status

Required. Starts, stops, or displays service contract dictionary settings for specific services, or all services if none are specified. A start or stop request for a service that has already activated or deactivated contract discovery is ignored. Effective service information is displayed when handling the requests.

(i) Note

 $\mathtt{start} \, | \, \mathtt{stop} \, | \, \mathtt{status} \, \, \mathtt{must} \, \, \mathtt{occur} \, \, \mathtt{after} \, \, \mathtt{-e} \, \, \mathtt{and} \, \, \mathtt{-f} \, \, \mathtt{,} \, \, \mathtt{if} \, \, \mathtt{either} \, \, \mathtt{of} \, \, \mathtt{those} \, \, \mathtt{options} \, \, \mathtt{are} \, \, \mathtt{specified}.$

[-e]

Specifies the service scope as a regular expression.



[-f <file>]

The service scope is defined in the given <file>. The file may contain sections to group related definitions together. All entries for a section must be written together line-by-line.

Empty lines or lines starting with '#' are ignored. Lines starting with '*' are section lines. Other lines are "id=content" definitions.

```
id1 id2 ...
```

Indicates one or more services. If -e is specified, a regular expression is used to match the service name. If -e is not specified, the service name is matched exactly.

1.3.5 Example(s)

Example 1 - start discovery for TOUPPER, TOLOWER:

```
tmscd start TOUPPER TOLOWER
```

Example 2 - start discovery for services started with TO and BR:

```
tmscd -e start TO.* BR.*
```

Example 3 - same request as example 1 but via file:

tmscd -f svcfile start id1 id2

(i) Note

The first found definition is used if section is not provided:

Example 4 - same request as example 2 but via file:

```
tmscd -e -f svcfile start case4.svcs
```

Example 1-8 svcfile Content

The following example shows content of the file named svcfile

```
# file: svcfile
*case3
id1 = TOUPPER
id2 = TOLOWER

*case4
svcs = TO.*|BR.*
```

1.3.6 Diagnostics

tmscd fails if Tmmetadata is not booted or booted using the -r (readonly) option without the -o option.



(i) See Also

TMMETADATA(5)

Configuring Service Contract Discovery in the SALT Configuration Guide SALT Web Service Definition File Reference

1.4 tmwsdlgen

- **Name**
- **Synopsis**
- Description
- Deprecation
- **Diagnostics**
- Example(s)

1.4.1 Name

tmwsdlgen - WSDL document generator.

1.4.2 Synopsis

```
tmwsdlgen -c wsdf_file [-y] [-o wsdl_file] [-m {pack|raw|mtom}] [-t
{wls|axis}]
```

1.4.3 Description

tmwsdlgen generates a WSDL document file from a Tuxedo native Web Service Definition File (WSDF). The generated WSDL document is WSDL 1.1 specification compliant, and represents both the service contracts and policies. tmwsdlgen collects Tuxedo service contract information throughout the Tuxedo Service Metadata Repository management (TMMETADATA) process. tmwsdlgen works as a Tuxedo native client and requires the following:

- the TUXCONFIG environment variable must be set correctly
- the relevant Tuxedo application using TMMETADATA must be booted prior to executing tmwsdlgen.



🛕 Warning

The given WSDF must be a Tuxedo native WSDF. Do not use a wsdlcvt converted non-native WSDF file as input.

tmwsdlgen accepts the following parameters:

-c wsdf file

Mandatory. Used to specify the SALT WSDF local path.



tmwsdlgen accepts the following optional parameters:

-o wsdl file

Used to specify the output WSDL document file path. If the option is not present, the default file, tuxedo.wsdl, is created in the current directory. If the specified WSDL document file already exists, then a prompt displays to confirm to overwriting the existing file.

Overwrites the existing WSDL document file without prompting.

-m

Used to specify the WSDL data mapping policy for certain Tuxedo typed buffers. Currently, it applies to the Tuxedo CARRAY buffer type. If raw mode is specified, CARRAY is represented to the MIME attachment. If pack mode is specified, xsd:base64Binary is used to represent CARRAY. The default value is pack mode.



(i) Note

raw mode cannot be used for .Net clients. The .Net Framework does not support MIME attachments.

If mtom is specified, CARRAY is mapped to the MTOM SOAP message.

This option takes effect only when the -m option is specified in raw mode. It accepts two options, wls or axis:

- wls indicates tmwsdlgen generates the WSDL document file in compliance with WebLogic 9.x. The default is wls.
- axis indicates the WSDL document file format can be recognized by the Apache Axis toolkit.

1.4.4 Deprecation

The following SALT 1.1 tmwsdlgen parameters are deprecated in the current release.

-c Config_file

Mandatory. Used to specify the SALT Configuration File path.



(i) Note

In the current SALT release, the SALT 1.1 configuration file is specified as the tmwsdlgen input using the following optional parameters:

Used to specify the encoding style used for Web service SOAP messages. Specifies rpc for RPC/encoded style and doc for Doc/literal encoded style. If this option is not present or the specified value is invalid, Doc is the default style.



-V

Used to specify the SOAP protocol version that the WSDL file supports. Specify 1.1 for SOAP 1.1 protocol and 1.2 for SOAP 1.2 protocol. If this option is not present or the specified value is invalid, SOAP 1.1 is used as the default.



In the current SALT release, the SOAP version and message style attribute are specified in the SALT WSDF.

1.4.5 Diagnostics

If a syntax error is detected in the given WSDF, an "ERROR" or "FATAL" message indicating that problem is printed to the standard error, and no WSDL file is generated and tmwsdlgen exits with exit code 1.

A "WARN" message is printed to the console if:

- 1. WSDF content may result in a potential run-time risk, or
- 2. Default values are used because they are not specified in the WSDF. "WARN" messages do not interrupt tmwsdlgen execution.

Upon successful completion, tmwsdlgen exits with exit code 0.

1.4.6 Example(s)

The following command generates a WSDL document file, Salt.wsdl, from the specified SALT WSDF. tux.wsdf

```
tmwsdlgen -c tux.wsdf -o Salt.wsdl
```

The following command generates a default WSDL document file with SOAP w/Attachment capability from the specified SALT WSDF, app_wsdf.xml.

tmwsdlgen -c app_wsdf.xml -m raw

See Also

GWWS(5)

wsdlcvt

SALT Web Service Definition File Reference

1.5 wsadmin

- Name
- Synopsis
- Description
- Example(s)



1.5.1 Name

wsadmin - SALT administration command interpreter.

1.5.2 Synopsis

wsadmin [-v]

1.5.3 Description

wsadmin uses specific commands to monitor and administrate active GWWS processes in the specified Tuxedo domain. The TUXCONFIG environment variable is used to determine the location where the Tuxedo configuration file is loaded. wsadmin is used in the same manner as tmadmin(1) or dmadmin(1).

wsadmin accepts below optional parameter:

Causes wsadmin to display the SALT version number, SALT Patch Level and license information. wsadmin exits after print out.

wsadmin Commands

Commands may be entered using either their full name or their abbreviation (as given in parentheses), followed by any appropriate arguments. Arguments appearing in brackets [], are optional; arguments in braces, {}, indicate a selection from mutually exclusive options.



Note

Command line options that are not in brackets do not need to appear in the command line if the corresponding default has been set via the default command.

wsadmin supports the following commands:

```
reload (reload) -i gwws_instance_id
```

Reload configuration for the specified GWWS gateway instance. The configuration file may have previously been modified using wsloadcf, this command is used to make the changes active.

```
configstats(cstat) -i gwws_instance_id
```

Displays the current configuration status for the specified GWWS process. The -i parameter must be specified.

```
default(d) [-i gwws_instance_id]
```

Sets the corresponding argument to the default GWWS Instance ID. The defaults can be changed by specifying * as an argument. If the default command is entered without arguments, the current defaults are printed.

```
echo(e) [{off | on}]
```

Repeats input command lines when set to on. If no option is given, the current setting is toggled, and the new setting is printed. The initial setting is off.



forgettrans (ft) -i gateway_instance_id [-c Coord_context]

Forgets one or all heuristic log records for the named GWWS instance. If the transaction identifier tran_id or coord_context coordination context is specified, only the heuristic log record for that transaction is forgotten. The coordination context (coord_context) can be obtained from the printtrans command or from the ULOG file.

help (h) [command]

Prints help messages. If command is specified, the abbreviation, arguments, and description for that command are printed.

Omitting all arguments causes the syntax of all commands to be displayed.

```
gwstats(gws) -i gwws_instance_id [-s serviceName]
```

Displays global level run time statistics information for the specified GWWS processes including fail, success, pending number for both inbound and outbound call, average processing time, active thread number, etc. If -s serviceName specified, the service-level information is displayed.

-i is mandatory. -s is optional.

```
paginate(page) [{off | on}]
```

Paginates output. If no option is given, the current setting is toggled, and the new setting is printed. The initial setting is on, unless either standard input or standard output is a non-tty device. Pagination may be turned on only when both standard input and standard output are tty devices.

The default paging command is indigenous to the native operating system environment. In a UNIX operating system environment, for example, the default paging command is pg. The shell environment variable PAGER may be used to override the default command used for paging output.

```
printtrans (pt) -i gateway_instance_id
```

Prints transaction information for the named GWWS instance. The output for each transaction record contains the following colon-delimited string fields:

```
process ID:GWWS instance id:service name:local
GTRID:remote coordination context ID:record
type:timestamp
```

quit (q)

Terminates the session.

saml create [-p password]

"saml create" is used to create a key file with the name "saml_key_meta" in the current working directory.

-p password

"saml create" command will use this as password to protect the key file. This tool will prompt user to enter password if this option is not given as part of command line argument.

The password option must be given whether to create the key file or in other operation to update the key file. The "password" is an administrative password for this key file. All the operations targeted at a key file must given the same password when the key file was first created.



Example(s):

Here is an example to create a key metadata file protected by password "password". saml create -p password

saml add {-g -s shared_secret |-i -n issuer_name [-l issuer_local_id]{[-c]
[-s shared_secret]}} [-p password]

"saml add" can be used to add an entry to an existing GWWS key file. The key file must have the name "saml_key_meta" in the current working directory. Either one of the "-g" and "-i" option must be given.

-g

Add an entry for GWWS to the key file. If the GWWS record already exists then this operation will fail. When "-g" option is given then "-n", "-l" and "-c" options are not allowed, if anyone of them is given the operation will fail.

-i

Add an entry for trusted SAML issuer. When this option is specified then "-n" option for SAML issuer name must also be specified.

-n

The trusted SAML issuer name as it appears in the "issuer" subelement or attribute of a SAML assertion.

-1

The local reference id of the trusted issuer. It is a short-hand name for easier reference.

-s

The shared secret. It is the symmetric key used by issuer to sign the assertion.

-c

This indicate that the public key certificate for trusted SAML issuer is installed. If this is not specified in the command line then GWWS will not be able to use public key to verify the signature if such signing is done if binary security token is not attached to the SOAP message.

-p

The password for accessing the key file. This is not optional and must be the same password given when this key file is created. This tool will prompt user to enter password if it is not given as part of command line argument.

Example(s):

Here is an example to add a GWWS record to a key file that is protected by password "password".

```
saml add -g -s mysecret -p password
```

The following is an example to add a trusted issuer record to a key file that is protected by password "password". The trusted issuer is configured with both public key certificate and a shared secret.

```
tSaml add -i -n saml.abc.com -l abc -s accessabc -c -p password
```

If the add operation target is trusted issuer and "-I" option is not given then the operation will use issuer name as local reference name by default. Also in this case either "-c" or "-s" must be given; if both are given then both information will be stored in the key file as part of trusted issuer record.



Both "-n" and "-l" option must be unique in the key file this means that no other trusted issuer has the same issuer name or local reference name. If a record with the same issuer name or same local reference exists then the operation will fail.

saml modify {-g -s shared_secret |-i {[-n issuer_name][-l issuer_local_id]}{[-c][-s shared_secret]} [-p password]

"saml modify" can be used to modify an entry to an existing GWWS key file; the entry can be either GWWS entry or trusted issuer entry. The key file must have the name "saml_key_meta" in the current working directory. Either one of the "-g" and "-i" option must be given.

-g Modify the GWWS entry in the key file. If the GWWS record does not exists then this operation will fail. When "-g" option is given then "-n", "-l" and "-c" options are not allowed, if anyone of them if given the operation will fail.

-i

Modify the trusted SAML issuer entry in the key file. When this option is specified then either "-n" or "-l" option for the issuer name must also be specified. If both "-n" and "-l" options are specified and there is no record matches both search criteria then the operation will fail.

-n

The trusted SAML issuer name as it appears in the "issuer" subelement or attribute of a SAML assertion.

-1

The local reference id of the trusted issuer. It is a short-hand name for easier reference.

-s

The shared secret. It is the symmetric key used by issuer to sign the assertion.

-c

This indicate that the public key certificate for trusted SAML issuer is installed. If this is not specified in the command line then GWWS will not be able to use public key to verify the signature if such signing is done if the binary security token is not attached to the SOAP message.

-p

The password for accessing the key file. This is not optional and must be the same password given when this key file is created. This tool will prompt user to enter the password if this option is not given as part of command line argument.

Example(s):

Here is an example to add a shared secret to the GWWS record in the key file that is protected by password "password".

```
saml modify -g -s mysecret -p password
```

The following is an example to add or modify a shared secret to a trusted issuer record in the key file that is protected by password "password".

```
saml modify -i -l abc -s accessabc -p password
```

The following is an example to remove a shared secret from a trusted issuer in the key file that is protected by password "password".



```
saml modify -i -l abc -s -p password
```

If the modify operation target is trusted issuer then only one of the "-n" and "-l" options is needed because both issuer name and local reference must be unique in the key file. If both "-n" and "-l" options are given then the record must match both; if no record matches both criteria then the operation will fail. If issuer is the target, i.e. "-i" option is given, and "-c" is not given then it will remove the certificate information from the record. If issuer is the target and "-c" is given then it will add the certificate information if it is not in the record originally.

If the "-s" option is given and the existing record already contains shared secret then the new shared secret will replace the old one. The "-s" option must be given with shared secret value specified. When the "-s" option is given with shared secret and the existing record does not have shared secret, then shared secret will be added to the record.

saml delete {-g|-i {-n issuer_name | -1 issuer_local_id}} [-p password] "saml delete" is used to delete an entry from an existing GWWS key file. The key file must have the name "saml_key_meta" in the current working directory. The entry can be either the GWWS entry or trusted issuer entry. Either "-g" or "-i" option must be given.

-6

Delete a GWWS entry from the key file. If the GWWS record does not exists then no operation will be performed. When this option is given then "-n" and "-l" options are not allowed.

-i

Delete a trusted SAML issuer entry from key file. When this option is specified then either "-n" or "-l" option for SAML issuer name must also be specified.

-n

The trusted SAML issuer name as it appears in the "issuer" subelement or attribute of a SAML assertion.

-1

The local reference id of the trusted issuer. It is a short-hand name for easier reference.

-p

The password for accessing the key file. This is not optional and must be the same password given when this key file is created. This tool will prompt user to enter password if this option is not part of command line argument.

Example(s):

Here is an example to delete a GWWS record from a key file that is protected by password "password".

```
saml delete -g -p password
```

The following is an example to delete a trusted issuer record from a key file that is protected by password "password".

```
Saml add -i -l abc -p password
```

```
verbose (v) [{off | on}]
```

Produces output in verbose mode. If no option is given, the current setting is toggled, and the new setting is printed. The initial setting is off.



!shellcommand

Escapes to the shell and executes shell command.

!!

Repeats previous shell command.

#[text]

Specifies comments. Lines beginning with # are ignored.

<CR>

Repeats the last command.

1.5.4 Example(s)

 The following command inspects run time statistics for both inbound and outbound service on GW2

```
wsadmin
> gws -i GW2
GWWS Instance : GW2
Inboud Statistics :
_____
Request Response Succ: 3359
Request Response Fail : 0
Oneway Succ : 0
Oneway Fail: 0
Total Succ: 3359
Total Fail: 0
Avg. Processing Time: 192.746 (ms)
Outboud Statistics :
_____
Request Response Succ : 4129
Request Response Fail: 0
Oneway Succ : 0
Oneway Fail: 0
Total Succ: 4129
Total Fail : 0
Avg. Processing Time: 546.497 (ms)
_____
Total request Pending : 36
Outbound request Pending: 0
Active Thread Number: 141
```

2. The following command inspects run time statistics for the ToUpperWS service on GW1 and gets output in verbose mode.

```
wsadmin
> > verbose
Verbose now on.
> gws -i GW1 -s ToUpperWS
```



```
GWWS Instance : GW1
Service : ToUpperWS
Outboud Statistics :
-----
Oneway Succ : 0
Oneway Fail : 0
-----
Avg. Processing Time : 0.000 (ms)
```

(i) See Also

GWWS(5)

SALT Administration Guide

1.6 wscobolcvt

- Name
- Synopsis
- Description
- Parameters
- Examples

1.6.1 Name

wscobolcvt – Generates SALT artifacts from COBOL copybook for exposing COBOL service as a web service.

1.6.2 Synopsis

wscobolcvt -c <copybook> -s <mainframe svc name> -r <metadata.repos> -S <MIF
web service name> [-L <local domain name:group> -R <remote domain name> -A
<CRM address>]

1.6.3 Description

wscobolcvt parses a COBOL copybook file to generate service metadata that reflects the structure of the COBOL record present in the file.

It also optionally adds TMA configuration in the form of local and remote domain definitions, as well as SNACRM definitions to the /Domains configuration.

1.6.4 Parameters

wscobolcvt uses the following options:



-c[ioe] <copybook>

Specifies the copybook file to parse. The optional [ioe] suboptions are used to specify different copybooks for input, output and error respectively. Suboptions can be combined, i.e., use -cioe <copybook> to use the same copybook for all instances, -cio for using the same copybook for input or output (no error buffer generated), -c, -ci or -co used alone defaults to the same copybook being used for both input and output. Valid -c[ioe] combinations are:

- -c, -ci, -co or cio <copybook>: Copybook used for input and output buffers, no error buffer.
- -ce, -cie or -coe <copybook>: Copybook used for input, output and error buffers.-ci
 <copybook1> -co <copybook2> [-ce <copybook3>]: copybook1 used for input and copybook2 used for output, optionally copybook3 used for error

-s <mainframe service name>

Specifies the mainframe service name.

-r <metadata repository file>

Specifies the name of the Tuxedo service repository file.

-S <MIF web service name>

Specifies the name of the web service that will be generated.

-L <local domain name:group>

Optional. Specifies a local domain ID to be added to DMCONFIG, including UBBCONFIG group to which it will belong.

-R <remote domain name>

Optional. Specifies a remote domain ID to be added to DMCONFIG.

-A <CRM address>

Optional. Specifies the address of the SNA CRM.



You must be an Oracle Tuxedo administrator in order to perform /Domains automatic configuration.

1.6.5 Examples

The following example is a COBOL copybook record:

Example 1-9 COBOL copybook record

```
* customer.cpy
01 CUSTOMER.
05 name PIC X(10).
05 balance PIC S9(9) COMP-5.
05 address PIC X(80).
```

The following example generates Tuxedo service metadata from a COBOL copybook file:

```
$ wscobolcvt -c customer.cpy -s CUST -r meta.repos -S wsCUST
```



(i) See Also

SALT Mainframe Transaction Publisher in Configuring a SALT Application

1.7 wsdlcvt

This section contains the following topics:

- Name
- Synopsis
- Description
- Parameters
- Environment Variable(s)
- Diagnostics
- Example(s)

1.7.1 Name

wsdlcvt - WSDL document converter.

1.7.2 Synopsis

1.7.3 Description

wsdlcvt is used to convert an existing WSDL 1.1 document to a Metadata Input File, FML32 mapping File and SALT Web Service Definition File (WSDF). It is a wrapper script for wsdl2mif.xsl, wsdl2fml32*.xsl and wsdl2wsdf.xsl for Xalan. Apache Xalan 2.7 libraries are bundled with SALT product.

JRE 1.5 or higher is required to run wsdlcvt.

1.7.4 Parameters

wsdlcvt accepts the following parameters:

-i

Specifies the URL of the input WSDL document. The URL can be a local file path or a downloadable HTTP URL link.

-0

Specifies the output files basename. The following suffixes are appended after the basename:



Table 1-2 wsdlcvt-Created File Suffixes

Suffix	Output File
.mif	Tuxedo Service Metadata Input File
.fm132	FML32 Field Table Definition File
.wsdf	SALT Web Service Definition File
.xsd	The WSDL Document embedded XML Schema File

wsdlcvt accepts the following optional parameters:

-f

Forces generation of service metadata information necessary for the conversion of Oracle Tuxedo fields into/from XML attributes (which is not done by default).

-у

Specifies that all the output destination files are overwritten without prompting if they exist. If this parameter is not specified, a prompt message is output.

-m

Specifies that the "xsd:string" data type is mapped to an FML32 typed buffer Tuxedo FLD_MBSTRING data type. If this parameter is not specified, Tuxedo FLD_STRING data type is mapped by default.

-v

Specifies that wsdlcvt works in verbose mode. In particular, it shows context information in the message and output context as FML32 field comments.

-w

If the given WSDL document is published using Microsoft .NET WCF, and it includes the wsdl:import tag, this parameter is specified to ensure that it is correctly handled by wsdlcvt.

-sh

Specifies the SOCKS proxy host name to use when a network connection needs to be established (for instance to download the WSDL document from a remote host). This can be a hostname or an IP address. If the proxy name is incorrect and a connection can not be established, wsdlcvt will attempt to connect directly.

-sp

Specifies the SOCKS proxy host port number to use if necessary in conjunction with the -sh option. The default value is 1080.

-C

Indicates that COBOL copybooks are generated from the processed WSDL. One record (i.e., lowest level structure), is generated per direction of message in a single file name <output_basename>.cpy.

Optionally (and only if -C is used), users with Oracle Tuxedo administrator permissions are also able to add /Domains configuration in the form of the following arguments:

-L <local domain name:group>

Optional. Specifies a local domain ID to be added to DMCONFIG, including UBBCONFIG group to which it will belong



-R <remote domain name>

Optional. Specifies a remote domain ID to be added to DMCONFIG

-A <CRM address>

Optional. Specifies the address of the SNA CRM

-D

Default COBOL char maxlength. When xsd:string types are not size-constrained, they are generated with a default of 256 (PIC X(256)) if -D is not specified, or the value specified by this option. Value is a positive integer between 2,147,483,647.

1.7.5 Environment Variable(s)

The TUXDIR and LANG environment variables must be set correctly.

The PATH environment variable must be set appropriately to execute "java".

1.7.6 Diagnostics

Error, warning or information messages are output to standard output.

1.7.7 Example(s)

The following command converts the local WSDL file, sample.wsdl.

```
wsdlcvt -i sample.wsdl -o sample
```

The following command converts a WSDL document from a HTTP URL link. The "xsd:string" data type is mapped to the Tuxedo FLD MBSTRING field type.

```
wsdlcvt -i sample.wsdl -o sample
```

(i) See Also

Creating the Oracle Tuxedo Service Metadata Repository

field tables(5)

SALT Web Service Definition File Reference

1.8 wsloadcf

- Name
- Synopsis
- Description
- Environment Variables
- Diagnostics



1.8.1 Name

wsloadcf - Reads SALT Deployment file and other referenced artifacts. Loads a binary SALTCONFIG file.

1.8.2 Synopsis

```
Usage 1: wsloadcf [-n][-y][-D \log evel] saltdeploy_file Usage 2: wsloadcf [-n][-y][-D \log evel] -1 [-s rpc|doc][-v 1.1|1.2] salt_1.1_config
```

1.8.3 Description

wsloadcf reads a SALT deployment file and other referenced files (WSDF files, WS-Policy files), checks the syntax, and optionally loads a binary SALTCONFIG file. The SALTCONFIG environment variable points to the SALTCONFIG file where the information should be stored. The generated SALTCONFIG file is necessary to boot GWWS servers.

wsloadcf accepts the following optional parameters:

-n

Do validation only without generating the SALTCONFIG file.

-у

After checking the syntax, tmloadcf checks whether: (a) the file referenced by SALTCONFIG exists; (b) it is a valid Oracle Tuxedo system file system; and (c) it contains SALTCONFIG tables. If these conditions are not true, wsloadcf prompts you to indicate whether you want the command to create and initialize SALTCONFIG.

Initialize SALTCONFIG file: path [y, q]?

Prompting is suppressed if the -y option is specified on the command line.

-D

Used to specify the configuration parsing log level.

For SALT 1.1 backward compatibility, wsloadcf can also read a SALT 1.1 configuration file. Besides generating the SALTCONFIG binary file, wsloadcf also generates one SALT Web Service Definition File (WSDF) and one SALT Deployment file according to the given SALT 1.1 configuration file.

-1

Turns on the SALT 1.1 compatible mode. To pass the SALT 1.1 configuration file to wsloadcf, you must specify this flag first.

-v

Only takes effect when a SALT 1.1 configuration file is used. This option is used to specify which SOAP version is applied to the generated WSDF file.

-8

Only takes effect when a SALT 1.1 configuration file is used. This option is used to specify which SOAP message style is applied to the generated WSDF file.



1.8.4 Environment Variables

The SALTCONFIG environment variable must be set before executing wsloadcf.

1.8.5 Diagnostics

If a syntax error is detected in the given configuration files, an "ERROR" or "FATAL" message indicating that problem is printed to the console, and no information is updated in the SALTCONFIG file. wsloadcf exits with exit code 1.

A "WARN" message is printed to the console if: (1) configuration files may result in a potential run-time risk or (2) default values are used because they are not specified in the configuration files. "WARN" messages do not interrupt wsloadcf execution.

Upon successful completion, wsloadcf exits with exit code 0. If the SALTCONFIG file is updated, a userlog message is generated.

See Also

SALT Web Service Definition File Reference

SALT Deployment File Reference

1.9 wsunloadcf

- Name
- Synopsis
- Description
- Environment Variables

1.9.1 Name

wsunloadcf — Reads a binary SALTCONFIG file, creates a SALT deployment file and other referenced files (WSDF files, WS-Policy files).

1.9.2 Synopsis

Usage: wsunloadcf

1.9.3 Description

wsunloadcf reads a binary SALTCONFIG file, creates a SALT deployment file and other referenced files (WSDF files, WS-Policy files). The SALTCONFIG environment variable points to the SALTCONFIG file where the information should be stored.

1.9.4 Environment Variables

The SALTCONFIG environment variable must be set before executing wsunloadcf.



(i) See Also

SALT Web Service Definition File Reference

SALT Deployment File Reference

SALT Web Service Definition File Reference

The following sections provide SALT Web Service Definition File (WSDF) reference information:

- Overview
- **SALT WSDF Format**
- XML Schema
- **SALT WSDF Examples**
- **SALT WSDF Element Descriptions**

2.1 Overview

The SALT Web Service Definition File (WSDF) is an XML-based file used to define SALT Web service components (for example, Web Service Bindings, Web Service Operations, Web Service Policies, and so on). WSDF is a SALT specific representation of the Web Service Definition Language data model. There are two WSDF types:

Native WSDF (Tuxedo generated) A native WSDF is composed manually. You must define a set of Tuxedo services and how they are exposed as Web services in a native WSDF. The native WSDF is similar to the SALT 1.1 configuration file.



(i) Note

A native WSDF is the input file used by the SALT WSDL generator (tmwsdlgen).

Non-native WSDF (Externally generated)

A non-native WSDF is generated from an external WSDL file via the SALT WSDL converter (wsdlcvt). In most cases, you do not need to change the generated WSDF except for configuring advanced features.

For more information, see tmwsdlgen and wsdlcvt in the SALT Reference Guide.

2.2 SALT WSDF Format

The following figure shows a graphical representation of the WSDF format.



<Definition> No annotation: Exactly one *: Zero or more <WSBinding> * +: One or more ?: Zero or one <Servicegroup> <Policy> ' <Service> * <Policy> * <Input>? <Msghandler> ? <Output> ? <Msghandler> ? <Fault> ? <Msghandler>? <Property> <SOAP> <AccessingPoints> <Endpoint> <Realm> ?

Figure 2-1 SALT Web Service Definition File Format:

2.3 XML Schema

An XML Schema is associated with the \mathtt{WSDF} . The XML Schema file that describes the \mathtt{WSDF} format is located in the following directory: $\mathtt{TUXDIR}/\mathtt{udataobj/salt/wsdf.xsd}$.

2.4 SALT WSDF Examples

The following shows native and non-native WSDF examples:



Example 2-1 Native WSDF (Composed Manually)

```
<Definition name="bankapp"</pre>
  xmlns=http://www.bea.com/Tuxedo/WSDF/2007 >
  <WSBinding id="bankapp binding" >
    <Servicegroup id="bankapp">
      <Policy location="/home/user/rm.xml" />
      <Service name="inquiry" />
      <Service name="deposit" />
    </Servicegroup>
    <SOAP>
      <AccessingPoints>
        <Endpoint id="HTTP1" address="http://myhost:7001" />
        <Endpoint id="HTTPS1" address="https://myhost:7002/bankapp" />
      </AccessingPoints>
    </SOAP>
  </ WSBinding >
</Definition>
```

Example 2-2 Non-Native WSDF (Generated from an External WSDL Document)

```
<Definition name="myWebservice"</pre>
  wsdlNamespace="http://www.example.org/myWebservice"
  xmlns=http://www.bea.com/Tuxedo/WSDF/2007 >
  <WSBinding id="A_binding">
    <Servicegroup id="portType">
      <Service name="operation_1" soapAction="op1" />
      <Service name="operation_2" soapAction="op2" />
    </Servicegroup>
    <SOAP version="1.1" style="rpc" use="encoded">
      <AccessingPoints>
        <Endpoint id="example_http_port"</pre>
                  address="http://www.example.org/abc" />
        <Endpoint id="example_https_port"</pre>
                  address="https://www.example.org/abcssl" />
      </AccessingPoints>
    </SOAP>
  </WSBinding>
  <WSBinding id="B_binding">
    <Servicegroup id="portType">
      <Service name="operation_3" soapAction="op3" />
      <Service name="operation_4" soapAction="op4" />
    </Servicegroup>
    <SOAP version="1.2">
      <AccessingPoints>
        <Endpoint id="another_http_port"</pre>
                  address="http://www.example.org/def" />
      </AccessingPoints>
    </SOAP>
  </WSBinding>
</Definition>
```



2.5 SALT WSDF Element Descriptions

WSDF format elements and their attributes are listed and described in the following section:

- <<u>Definition></u>
- <WSBinding>
- <Servicegroup>
- <Service>
- <Input>
- <Output>
- <Fault>
- <Msghandler>
- <Policy>
- <<u>Property></u>
- < < SOAP >
- <AccessingPoints>
- <Endpoint>
- <Realm>

2.5.1 < Definition >

The WSDF file root element.

Table 2-1 Definition Attributes

Attribute	Description	Require
name	The WSDF name. This attribute value may contain a maximum of 30 characters (excluding the terminating NULL character).	Yes
	Native WSDF: you must manually provide a distinct application name.	
	Non-native WSDF: this value is the same as the WSDL converter (wsdlcvt) command line input parameter "output_basename".	



Table 2-1 (Cont.) Definition Attributes

Attribute	Description	Require
wsdlNamespace	The corresponding WSDL document target namespace for the WSDF. Native WSDF: you can optionally specify a distinct URI string so that the generated WSDL can use this as the target namespace. If not specified, the default WSDL target namespace is as follows: "urn: <wsdf_name>.wsdl". For example, if the WSDF name is "simpapp", then the default WSDL target namespace is "urn:simpapp.wsdl". Non-native WSDF: the value is the WSDL target namespace of the external WSDL document.</wsdf_name>	No

2.5.2 <WSBinding>

Defines concrete protocol binding information. Zero or more WSBinding objects can be specified in one WSDF file.

Native WSDF: you can set SOAP version, encoding style, several endpoints for Web Service Client connection through sub element <SOAP> and a set of Tuxedo services to be exposed for invocation through sub element <Servicegroup>

Non-native WSDF: each SOAP binding object (i.e., wsdl:binding object with soap:binding extension) in the external WSDL document is translated into one WSBinding object.

Table 2-2 WSBinding Attributes

Attribute	Description	Required
id	Identifies the WSBinding object. The value must be unique within the WSDF. This attribute value may contain a maximum of 78 characters (excluding the terminating NULL character).	Yes
	Native WSDF: the value is specified by customers and is used as the wsdl:binding name in the generated WSDL document.	
	Non-native WSDF: the value is the wsdl:binding name defined in the external WSDL document.	



2.5.3 <Servicegroup>

Defines a Servicegroup object for one WSBinding object. Each WSBinding object must have exactly one Servicegroup. The Servicegroup object is used to encapsulate a set of Tuxedo services.

Table 2-3 <Servicegroup> Attributes

Attribute	Description	Required
id	Specifies the service group id. This attribute value may contain a maximum of 78 characters (excluding the terminating NULL character). Native WSDF: the value is specified by customers and is used as the wsdl:portType name in the generated WSDL document.	Yes
	Non-native WSDF: the value is the wsdl:portType name defined in the external WSDL document.	

2.5.4 <Service>

Specifies a service for the WSBinding object.

- Native WSDF: Each service is a Tuxedo service.
- Non-native WSDF: Each service represents a converted Tuxedo service from a wsdl:operation object defined in the external WSDL document.

Attribute	Description	Required
name	Specifies the service name. This attribute value may contain a maximum of 255 characters (excluding the terminating NULL character). Native WSDF: the service name value is used as the wsdl:operation name in the generated WSDL document. Non-native WSDF: the service name is equal to the wsdl:operation name defined in the external WSDL document.	Yes
tuxedoRef	An optional attribute used to reference the service definition in the Tuxedo Service Metadata Repository. If not specified, attribute "name" value is used as the reference value.	No



Attribute	Description	Required
soapAction	Specifies the service soapAction attribute. This is a non- native WSDF attribute. It is used to save the soapAction setting for each wsdl:operation defined in the external WSDL document.	No
	Note Do not specify this attribute for a native WSDF.	
namespace	Specifies service namespace attribute. For non-native WSDF, it is used to save the namespace setting for each wsdl:operation defined in the external WSDL document. For native WSDF, all elements in SOAP message response use this namespace unless "paramschema" is specified for the matched parameter.	No
headerMapping	This service will put/retrieve data to/from SOAP header when invoked/performing an invocation. The data is taken/placed from/to the application buffer based on the service metadata "access" parameter settings. See "inheader/outheader/errheader" values for	-
	"access" in keyword in Managing The Oracle Tuxedo Service Metadata Repository documentation.	

2.5.5 <Input>

Specifies Input message attributes for a particular service. This element is optional.

Table 2-4 Input Attributes

Attribut e	Description	Require d
name	Specifies the service input message name attribute. This is a non-native WSDF attribute. It is used is used to save the name for the input wsdl:message defined in the external WSDL document.	
	Note Do not specify this attribute for a native WSDF.	



Table 2-4 (Cont.) Input Attributes

Attribut e	Description	Require d
wsaAct ion	Specifies the service input message wsaAction attribute. This is a non-native WSDF attribute. It is used is used to save the wsaAction attribute of the input wsdl:message defined in the external WSDL document. (i) Note Do not specify this attribute for a native WSDF.	No
encodi ng	Specifies the encoding to use when the message is outgoing (outbound request).	-

2.5.6 < Output>

Specifies Output message attributes for a particular service. This element is optional.

Table 2-5 Output Attributes

Attribut e	Description	Require d
name	Specifies the service output message name attribute. This is a <i>non-native</i> WSDF attribute. It is used to save the name for the output wsdl:message defined in the external WSDL document.	
	Note Do not specify this attribute for a native WSDF.	
wsaAct ion	Specifies the service output message name attribute. This is a <i>non-native</i> WSDF attribute. It is used to save the wsaAction attribute of the output wsdl:message defined in the external WSDL document.	
	Note Do not specify this attribute for a native WSDF.	
encodi ng	Specifies the encoding to use when the message is outgoing (inbound request).	-

2.5.7 < Fault>

Specifies Fault message attributes for a particular service. This element is optional.



Table 2-6 Fault Attributes

Attribut e	Description	Require d
name	Specifies the service fault message name attribute. This is a <i>non-native</i> WSDF attribute. It is used to save the name for the fault wsdl:message defined in the external WSDL document.	
	Note Do not specify this attribute for a native WSDF.	
wsaAct ion	Specifies the service fault message wsaAction attribute. This is a non-native WSDF attribute. It is used to save the wsaAction attribute of the fault wsdl:message defined in the external WSDL document.	
	Note Do not specify this attribute for a native WSDF	

2.5.8 < Msghandler >

Specifies a customized message conversion handler. Optional for !nput><a href=

The GWWS server looks for the message conversion handler from all known message conversion plug-in shared libraries using the handler name. The message conversion handler allows you to develop customized Tuxedo buffer and SOAP message payload transformation functions to replace the default GWWS message conversions.

For more information, see Programming Message Conversion Plug-ins in the SALT Programming Web Services.

2.5.9 < Policy >

References one Web Service Policy file applied to one of the following two levels:

- <Servicegroup> level
- <Service> level

At most, 10 Web Service policies can be referenced for each object.



Table 2-7 Policy Attributes

Attribute	Description	Required
location	Specifies the local file path for the referenced WS-Policy file. This attribute value may contain a maximum of 256 characters (excluding the terminating NULL character). Specifically, SALT pre-defines WS-Policy template files for typical WS-* scenarios. These files can be found under the \$TUXDIR/udataobj/salt/policy directory. You can reference these template files using the string format "salt: <template_file_name>". For example, if you want to reference SALT WS-SecurityPolicy 1.0 template file "wssp1.0-signbody.xml", you should define the following XML snippet in the WSDF file: <policy location="salt:wssp1.0-signbody.xml"></policy></template_file_name>	Yes



Table 2-7 (Cont.) Policy Attributes

Attribute	Description	Required
use	Specifies if the WS-Policy file is applied to the input message, output message, fault message, or the combination of the three. If multiple messages are set, use a space as the delimiter. For example, if you want to configure a WS-Policy file "mypolicy.xml" to be applied to "input" and "output" messages, you should define the following XML snippet in the WSDF file:	No
	<pre><policy location="mypolicy.xml" use="input output"></policy> SALT limits the applicable messages for each supported WS-Policy assertion.</pre>	
	For more information, see the following sections: • Configuring Advanced Web Service Messaging Features" in the SALT Configuration Guide	
	Configuring Message-Level Web Service Security in the SALT Configuration Guide SALT WS-	
	ReliableMessaging Policy Assertion Reference SALT WS-SecurityPolicy Assertion 1.2 Reference SALT WS-SecurityPolicy Assertion 1.0 Reference	

2.5.10 < Property >

Specifies SALT specific properties for each service object.

Table 2-8 Property Attributes

Attribute	Description	Required
name	Specifies the property name. The <property> Name List lists all the GWWS server properties.</property>	Yes
value	Specifies the property value.	Yes

The following table lists all properties that can be specified for each service object:



Table 2-9 < Property > Name List

Property	Description	Values
async_timeout	Outbound service: Specifies a time setting to wait for SOAP response. Inbound service: No behavior impact.	(0-32767] (sec) Default: 60 secs.
disableWSAddressing	Outbound service: Disables explicit Web Service Addressing requests with this property. Inbound service: No behavior impact.	{True False} Default: False
ignore_namespace	Removes namespaces from XML typed buffers before they are handed to Tuxedo services and puts them back before a response is sent to a web service client. Only applies to native Tuxedo services exposed as web services.	{True False} Default: False

Table 2-10 Property headerMapping

Property	Description	Values
headerMapping	When true, puts/retrieves data to/from SOAP header when invoked/performing an invocation. The data wis taken/placed from/to the application buffer based on the service metadata "access" parameter settings. See "inheader/outheader" values for "access" keyword in service metadata repository documentation.	{True False} Default: False

2.5.11 <SOAP>

Specifies SOAP protocol information for the WSBinding object. SOAP version, message style accessing endpoints are specified in this element.

Table 2-11 SOAP Attributes

Attribute	Description	Required
version	Specifies SOAP version for this WSBinding object. The valid values are "1.1" and "1.2". If not specified, "1.1" is used.	No



Table 2-11 (Cont.) SOAP Attributes

Attribute	Description	Required
style	Specifies SOAP message style for this WSBinding object. The valid values are "rpc" and "document". If not specified, "document" is used.	No
use	Specifies SOAP message encoding style for this WSBinding object. The valid values are "encoded" and "literal". If not specified explicitly, this value is automatically selected according to "style" value. If "style" is "rpc", then "encoded" is used; if "style" is "document", then "literal" is used.	No

(i) Note

In the current SALT release, only " $\protect\operatorname{rpc/encoded}$ " and "document/literal" are supported.

2.5.12 <AccessingPoints>

Specifies the endpoint list for the WSBinding object. Each sub element <Endpoint> represents one particular endpoint.

There is no attribute for this element.

2.5.13 < Endpoint >

Specifies each accessing endpoint for the WSBinding object.

Table 2-12 Endpoint Attributes

Attribut e	Description	Require d
id	Specifies a unique endpoint id value within the WSBinding object. This attribute value may contain a maximum of 78 characters (excluding the terminating NULL character).	Yes
addres s	Specifies the endpoint address. The address value must use the following format: "http(s):// <host>:<port>/<context_path>"</context_path></port></host>	
	Note Two endpoints cannot be specified with exact the same address URL value.	



2.5.14 < Realm >

Specifies the HTTP Realm attribute of an HTTP and/or HTTP/S endpoint. If this element is configured for one endpoint, the GWWS tries to incorporate HTTP basic authentication information in the request messages when issuing outbound calls through this endpoint.

For more information, see Configuring Transport-Level Security in the SALT Configuration Guide.



① Note

This element only works for non-native (external) WSDF files.

SALT Deployment File Reference

The following sections provide SALT Deployment File reference information:

- Overview
- SALT SALTDEPLOY Format
- XML Schema

3.1 Overview

The SALT Deployment File (SALTDEPLOY) is an XML-based file used to define SALT GWWS server deployment information on a per Tuxedo machine basis. SALTDEPLOY does the following:

- lists all necessary Web Service Definition Files (WSDF)
- specifies how many GWWS servers are deployed on a Tuxedo machine
- associates inbound and outbound Web Service access endpoints for each GWWS server.

SALTDEPLOY also provides a system section to configure global resources (for example certificates, plug-in load libraries, and so on).

3.2 SALT SALTDEPLOY Format

The following figure shows a graphical representation of the SALT SALTDEPLOY file format:



<Deployment> No annotation: Exactly one <WSDF> * : Zero or more +: One or more <import> * ?: Zero or one <WSGateway> <GWInstance> * <Inbound>? <Binding> * <Endpoint> + <HTTP>? <Network> <Service> * <Method> + <Outbound>? <Binding> * <WSAddressing> ? <Endpoint> <Endpoint> * <HTTP>? <Service> * <TLogDevice>* <TLogName>* <WSATEndpoint>* <MaxTran>* <Properties> ? <System> <Property> * <Certificate> ? <PrivateKey> <VerifyClient> ? <TrustedCert> ? <CertPath> ? <Plugin> ?

Figure 3-1 SALT Deployment File Format

3.3 XML Schema

An XML Schema is associated with a SALT SALTDEPLOY file. The XML Schema file that describes the SALT SALTDEPLOY file format is located in the following directory: \$TUXDIR/udataobj/salt/saltdep.xsd.

This section contains the following topics:

SALT SALTDEPLOY Example



- SALT SALTDEPLOY Element Descriptions
- <<u>Deployment></u>

3.3.1 SALT SALTDEPLOY Example

The following example shows a sample SALT SALTDEPLOY File.

Example 3-1 SALT SALTDEPLOY File

```
<Deployment xmlns="http://www.bea.com/Tuxedo/SALTDEPLOY/2007">
    <WSDF>
        <Import location="/home/myapp/bankapp.wsdf" />
        <Import location="/home/myapp/amazon.wsdf" />
    </WSDF>
<WSGateway>
    <GWInstance id="GW1">
        <Inbound>
            <Binding ref="bankapp:bankapp_binding">
                <Endpoint use="http1"/>
                <Endpoint use="https1" />
            </Binding>
        </Inbound>
        <Outbound>
            <Binding ref="amazon:default binding"/>
        </Outbound>
        <Properties>
            <Property
                name="socksAddrList"
                value="proxy.server.com,10.123.10.10:1080"/>
        </Properties>
    </GWInstance>
</WSGateway>
 <System>
    <Certificate>
        <PrivateKey>/home/user/cert.pem</PrivateKey>
    </Certificate>
    <Plugin>
        <Interface library="/home/user/mydatahandler.so" />
    </Plugin>
 </System>
</Deployment>
```

3.3.2 SALT SALTDEPLOY Element Descriptions

SALTDEPLOYF format elements and their attributes are listed and described in the following section.

3.3.3 < Deployment >

The SALTDEPLOY file root element.

There is no attribute for this element.



There can be only one <Deployment> element defined in a SALTDEPLOY file.

Three sections must be defined within the <Deployment> element:

- <WSDF>
- <WSGateway>
- <System>

3.3.3.1 < WSDF>

Top element that encapsulates all imported WSDF files.

There is no attribute for this element.

<Import>

3.3.3.1.1 < Import>

Specifies the WSDF to be imported in the SALTDEPLOY file. Multiple WSDF can be imported at the same time. Each WSDF file can only be imported once. Multiple WSDF with the same WSDF name cannot be imported in the same SALTDEPLOY file.

Table 3-1 ImportAttributes

Attribute	Description	Required
location	Specifies the WSDF local file path.	Yes

3.3.3.2 < WSG at eway >

Top element that encapsulates all GWWS instance definitions.

There is no attribute for this element.

<GWInstance>

3.3.3.2.1 < GWInstance >

Specifies a single GWWS instance.

Table 3-2 GWInstance Attributes

Attribute	Description	Required
id	Specifies the GWWS identifier. This attribute value may contain a maximum of 12 characters (excluding the terminating NULL character). The identifier value must be unique within the SALTDEPLOY file.	Yes

- <Inbound>
- <Outbound>
- <TLogDevice>



- <TLogName>
- <WSATEndpoint>
- <MaxTran>
- Properties

3.3.3.2.1.1 <Inbound>

Specifies inbound WSBinding objects for the GWWS server. Each inbound WSBinding object is specified using the Binding sub element.

There is no attribute for this element.

<HTTP>

3.3.3.2.1.1.1 < HTTP>

Specifies a list of services accessible in REST mode. All Oracle Tuxedo service names specified in this element are callable using HTTP or REST mechanisms. Any URL specifying a service not present on this list results in a 404 error for the caller. Any URL specifying a service present on this list (for which an Oracle Tuxedo service is not advertised), results in a 451 error for the caller.

There is no attribute for this element.

- <Network>
- <Service>

3.3.3.2.1.1.1.1 < Network>

This element contains two attributes specifying http or https (for SSL), HTTP/REST listening endpoints. Only one <Network> element is allowed per GWWS instance. The http and https elements are optional, but at least one must be specified. The http and https attributes are constructed as follows:

<host>: The name or IP address of the HTTP/REST listening endpoint.

<port>: The port value of the HTTP/REST listening endpoint.

All HTTP/REST requests are performed by the same <host>:<port> combination (that is, it is not possible to use more than one such combination per gateway, per protocol (http and https).

Table 3-3 Network Attributes

Attribute	Description	Required
http	HTTP host and port listening endpoint for REST requests. Format is a string containing a <host>:<port> pair corresponding to: <host> = name or IP address of the HTTP/REST listening endpoint.</host></port></host>	No*
	<pre><port> = port value of the HTTP/ REST listening endpoint.</port></pre>	
https	SSL HTTP host and port listening endpoint specification. Same format as http attribute.	No*



*While not required, the <Network> element must contain either an http or https attribute.

3.3.3.2.1.1.1.2 <Service>

Specifies a single service callable using HTTP/REST mechanisms. The actual Oracle Tuxedo service called is further qualified by an HTTP method as specified using the <Method> element.

Table 3-4 Service Attributes

Attribute	Description	Required
name	Name of Tuxedo service being advertised. (i) Note This is not the actual Oracle Tuxedo service configured using the <method> element.</method>	Yes
content-type	"JSON" represent "Content-Type: application/json", "XML" represent "Content-Type: application/xml". If request HTTP header has no content-type field, SALT will use the content-type attribute set here.	No
charset	Specifies the character encoding for the outgoing REST network message.	No

<Method>

3.3.3.2.1.1.1.2.1 < Method>

Specifies the HTTP method mapping to Oracle Tuxedo services. This is designed to model CRUD methods (Create, Read, Update, Delete).

Table 3-5 Service Attributes

Attribute	Description	Required
name	Method identifier, among GET, PUT, POST or DELETE. Any other value results in a configuration error.	Yes
service	Name of the Oracle Tuxedo service being mapped.	Yes
inputbuffer	Oracle Tuxedo buffer type/ optionally subtype used for input conversion. Values are the same as all existing Oracle Tuxedo buffer types. For VIEW/VIEW32 buffer types, the notion of subtype is conveyed by using the notation: {VIEW VIEW32}/ <subtype>, for example: VIEW32/customer.</subtype>	Yes



Table 3-5 (Cont.) Service Attributes

Attribute	Description	Required
reposservice	Reference to a metadata repository entry. This is used to associate interface data with an HTTP/REST service and method. One use is for the configuration tool to generate automatic test code based on service metadata (interface).	No
jsonTopLevelArray	If it is specified to "true", when the top level data of the inbound response is an array, GWWS returns a no-name json array at top level. The default value is "false".	No
enableRplyBuffer	If it is specified to "true", GWWS converts the TPFAIL error buffer to json message. The default value is "false".	No

3.3.3.2.1.2 < Outbound >

Specifies outbound WSBinding objects for the GWWS server. Each outbound WSBinding object is specified using the Binding sub element.

There is no attribute for this element.

- <Binding>
- <HTTP>

3.3.3.2.1.2.1 <Binding>

Specifies a concrete WSBinding object as either an inbound or outbound binding, depending on the parent element.

Table 3-6 Binding Attributes

Attribute	Description	Required
ref	Specifies a concrete WSBinding object using the following Qualified Name format: " <wsdf_name>: <wsbinding_id>"</wsbinding_id></wsdf_name>	Yes

Note

Please note the following maximum WSBinding object limitations for each GWWS server:

- Each GWWS server may reference at most 64 inbound WSBinding objects.
- Each GWWS server may reference at most 128 outbound WSBinding objects.



For TCP/IP addresses, one of the following formats is used as shown in the table below:

Table 3-7 Ipv4 and IPv6 Address Formats

IPv4	IPv6
//IP:port //[IPv6 address]:port	//[IPv6 address]:port
//hostname:port_number	//hostname:port_number
//#.#.#:port_number	Hex format is not supported

For more information, see TMUSEIPV6 in the TUXENV(5) environment variable listing found in the Tuxedo 10g R3 Reference Guide, Section 5 - File Formats, Data Descriptions, MIBs, and System Processes Reference.

- <Endpoint>
- <WSAddressing>

3.3.3.2.1.2.1.1 < Endpoint >

Specifies a single WSBinding objects endpoint reference.

If the referenced endpoint is specified as an inbound endpoint, the GWWS server creates the corresponding HTTP and/or HTTPS listen endpoint. At least one inbound endpoint must be specified for one inbound WSBinding object.

If the referenced endpoint is specified as an outbound endpoint, the GWWS server creates HTTP and/or HTTPS connections per SOAP requests for the outbound WSBinding object.

If an outbound endpoint is not specified for the outbound WSBinding object, the first 10 endpoints (at most) are auto-selected.

The referenced endpoint must already be defined in the WSDF.

Table 3-8 Endpoint Attributes

Attribute	Description	Required
use	The referenced endpoint id defined in the WSDF.	Yes

(i) Note

Please note the following maximum endpoints limitations for each GWWS server:

- Each GWWS server may create at most 128 inbound endpoints in all inbound WSBinding objects to accept SOAP requests.
- Each GWWS server may create connectivity with at most 256 outbound endpoints in all outbound WSBinding objects.

3.3.3.2.1.2.1.2 <WSAddressing>

Specifies if Web Service Addressing is enabled for the outbound WSBinding object.

If this element is present, by default all SOAP messages are sent out with a Web Service Addressing message header.



Table 3-9 WSAddressing Attributes

Attribute	Description	Required
version	Select WS-Addressing on-the- wire version to use 200408 for the "submission" version, and 200508 for version 1. If not defined, version defaults to 200408	No

The <WSAddressing> sub element <<u>Endpoint></u> must be specified for the listen endpoint address if this element is present.

<Endpoint>

3.3.3.2.1.2.1.2.1 < Endpoint >

Specifies the WS-Addressing listen endpoint address for the referenced outbound WSBinding object.

Table 3-10 Endpoint Attributes

Attribute	Description	Required
address	Specifies the WS-Addressing listen endpoint address.	Yes
	The address value must be in the following format:	
	"http(s):// <host>:<port>/ <context_path>"</context_path></port></host>	
	The GWWS server creates listen endpoints and usage for receiving WS-Addressing SOAP response messages.	

3.3.3.2.1.2.2 < HTTP>

Specifies a list of outbound services accessible in REST mode.

<Service>

3.3.3.2.1.2.2.1 <Service>

Specifies a outbound service callable using HTTP/REST mechanisms.

Table 3-11 Service Attributes

Attribute	Description	Required
name	Name of Tuxedo service being advertised.	Yes
content-type	"JSON" represent "Content-Type: application/json", "XML" represent "Content-Type: application/xml". If request HTTP header has no content-type field, SALT will use the content-type attribute set here.	No
charset	Specifies the character encoding for the outgoing REST network message.	No



3.3.3.2.1.3 <TLogDevice>

One attribute "location" describes the location of the Transaction file. This is required if WS-TX transaction support is required.

3.3.3.2.1.4 <TLogName>

One attribute "id" describes the name of the transaction log inside a Transaction file. This is required if WS-TX transaction support is required.

3.3.3.2.1.5 < WSATEndpoint >

One attribute address describes the WS-AT protocol end point.

3.3.3.2.1.6 < MaxTran>

One attribute "value" describes the maximum number of concurrent WS-TX transactions allowed. This is bounded by Oracle Tuxedo MAXGTT.

3.3.3.2.1.7 Properties

Top element that encapsulates all GWWS server property settings using the <Property> sub element.

Table 3-12 Properties Attributes

Attribute	Description	Required
socksAddrList	If necessary, endpoints can be grouped by GWInstance to achieve separation between proxy-using endpoints and non-proxy-using ones. Value: String type containing a list of proxy server URLs. For example: proxy.server1.com,10.123.1.1:1080.	Yes

Property

3.3.3.2.1.7.1 Property

Specifies one GWWS property.

Table 3-13 GWWS Property Attributes

Attribute	Description	Required
name	Specifies the property name. Table B-14 lists all the GWWS server properties.	Yes
value	Specifies the property value.	Yes



Table 3-14 GWWS Property List

Property	Description	Values
jwtConfigFileLo c	Enables customization of response messages upon JWT authentication failures and facilitates handling of additional JWT error codes.	The path to SALT JWT Configuration location.
max_content_len gth	Enables the GWWS server to deny the HTTP requests when the content length is larger than the property setting. If not specified, the GWWS server does not check for it. The string value can be one of the following three formats:	The equivalent byte size value must be in [1 byte, 1G byte]
	Integer number in bytes. No suffix means the unit is bytes.	range.
	2. Float number in kilobytes. The suffix must be 'K'. For instance, 10.4K, 40K, etc.	
	3. Float number in megabytes. The suffix must be 'M'. For instance, 100M, 20.6M, etc.	
thread_pool_siz	Specifies the maximum thread pool size for the GWWS server.	The valid value is in [1, 1024].
	① Note	Default value: 16
	This value defines the maximum possible threads that may be spawned in the GWWS server. When the GWWS server is running, the actual spawned threads may be less than this value.	
timeout	Specifies the network time-out value, in seconds.	The valid value is in [1, 65535] Default value: 300
max_backlog	Specifies the backlog listen socket value. It controls the maximum queue length of pending connections by operating system. Note: Generally no tuning is needed for this value.	The valid value is [1-255]. Default value: 16
enableMultiEnco ding	Toggles on/off multiple encoding message support for the GWWS server. If multiple encoding support property is turned off, only UTF-8 HTTP / SOAP messages can be accepted by the GWWS server.	The valid values are "true", "false".
enableSOAPValid ation	Toggles on/off XML Schema validation for inbound SOAP request messages if the corresponding Tuxedo input buffer is associated with a customized XML Schema.	The valid values are "true", "false". Default value: false



Table 3-14 (Cont.) GWWS Property List

Property	Description	Values
internalEncodin g	Mutually exclusive with enableMultiEncoding. Allows one-byte encodings such as the ISO-8859 series to map to non-MBSTRING types.	The valid values are "keepSame", one-byte encoding
	When it is set to a value other than "keepSame", SALT converts text in payloads to/from the specified encoding between the Tuxedo side (encoding translated based on the value of internalEncoding attribute) and the network side (SOAP or REST).	name such as the ISO-8859.
	This property must not be used with multi-byte encodings and in conjunction with MBSTRING buffers or fields; otherwise, a runtime error is thrown.	
wsrm_acktime	Specify the Reliable Messaging Acknowledgment message reply policy. GWWS servers support replying acknowledgment messages either after receiving the SOAP request from network immediately or after the Oracle Tuxedo	The valid values are "NETRECV", "RPLYRECV" Default value:
	service returns the response message.	"NETRECV"
enableCustomHTT PHeaders	Enable support for WEB WRITE/READ HTTPHEADER, interoperate with servers or clients that use HTTP headers to transmit data.	The valid values are "true" and "false".
		Default value: false
enableHTTPReque stLine	Description: Enable support for WEB READNEXT FORMFIELD, WEB EXTRACT HTTPMETHOD / QUERYSTRING/If its value set to "true", GWWS will add the Request-Line and URL-Protocol to request buffer Meta TCM.	The valid values are "true", "false". Default value: false
enableTPurcode	By default, this property is set to 'true' to enable tpurcode return HTTP error status for inbound SOAP cases. Set this property to 'false' will prevent tpurcode from returning any HTTP status. Set this property to 'outbound_rest' will enable tpurcode to return any HTTP status in outbound REST cases. Set this property to 'all' will enable the default behavior('true') and 'outbound_rest' behavior.	The valid values are "false", "true", "outbound_rest", "all" Default value: "true"
propagateECID	Toggles on/off ECID propagation support for the GWWS server. If propagate ECID support property is turned off, GWWS server will not propagate ECID.	The valid values are "true", "false". Default value: "true"
tuxedo_timeout	This property can be set to the maximum number of seconds that is allowed when an inbound request invokes a Tuxedo service. When invoking the Tuxedo service, the timeout will be the lesser of the tuxedo_timeout and any service level blocktime that is specified for the service.	The valid values are are from 0 to 65535. A value of 0 indicates that there is no Tuxedo timeout. The default value is
		0.

3.3.3.3 < System >

Specifies global settings, including certificate information, plug-in interfaces.

- <Certificate>
- <Plugin>



3.3.3.3.1 < Certificate >

Specifies global certificate information using sub elements < PrivateKey>, < VerifyClient>, < TrustedCert> and CertPath>

There is no attribute for this element.

Note

GWWS converts certificate to wallet when SEC_PRINCIPAL_PASSWORD is set. If only X509 certicates are used under HTTP, then there is no conversion.

- <PrivateKey>
- <VerifyClient>
- <TrustedCert>
- <CertPath>

3.3.3.3.1.1 < Private Key>

When using an Oracle wallet, specify the location of a directory that contains an Oracle Wallet.

(i) Note

SALT does not have the concept of a security principal name like Oracle Tuxedo does, so the Wallet is located in the specified directory and not in a sub-directory. To configure server identity certificates (SALT deploy configuration file <PrivateKey> element), it is required that the root certificate authority be present in the SSL configuration file. Proper configuration is:

- root CA certificate
- intermediate certificate(s) (if any)
- server certificate
- server private key
- · in PEM format.

When using the legacy security credentials format, specifies the PEM format private key file. The key file path is specified as the text value for this element. The server certificate is also stored in this private key file. The value of this element may contain a maximum of 256 characters (excluding the terminating NULL character).

With either security credential format, the password for the Oracle Wallet or the GWWS private key file is specifed in the ${\tt TUXCONFIG}$ file using the

SEC_PRINCIPAL_PASSVAR="environment_variable_name" parameter. The TUXCONFIG file must also set the SEC_PRINCIPAL_NAME="any_non-null_string(not_used)" parameter so that SEC_PRINCIPAL_PASSVAR will be properly processed in the configuration file.

This element is mandatory if the parent < Certificate > element is configured.



3.3.3.3.1.2 < Verify Client >

Specifies if Web service clients are required to send a certificate via HTTP over SSL connections. The valid element values are "true" and "false".

This element is optional. If not specified, the default value is "false".

3.3.3.3.1.3 < Trusted Cert >

Specifies the file name of the trusted PEM format certificate files. The value of this element may contain a maximum of 256 characters (excluding the terminating NULL character).

This element is optional.

3.3.3.3.1.4 < CertPath>

Specifies the local directory where the trusted certificates are located. The value of this element may contain a maximum of 256 characters (excluding the terminating NULL character).

This element is optional.



(i) Note

<VerifyClient> is set to "true", or if WS-Addressing is used with SSL, trusted certificates must be stored in the directory setting with this element. If only X509 certicates are used under HTTP, then there is no conversion.

3.3.3.3.2 < Plugin >

Specifies the global plug-in load library information. Each <Interface> sub element specifies one plug-in library to be loaded.

There is no attribute for this element.

<Interface>

3.3.3.3.2.1 < Interface >

Specifies one particular plug-in interface or a plug-in library for all plug-in interfaces inside the library.

Table 3-15 Interface Attributes

Attribute	Description	Required
library	Mandatory. Specifies a local shared library file path. This attribute value may contain a maximum of 256 characters (excluding the terminating NULL character).	Yes



Table 3-15 (Cont.) Interface Attributes

Attribute	Description	Required
params	Optional. Specifies a particular string value that is passed to the library when initialized by the GWWS server at boot time. This attribute value may contain a maximum of 256 characters (excluding the terminating NULL character).	No

For more information about how to develop a SALT plug-in interface, see Using SALT Plug-Ins *Programming Web Services*

SALT WS-AT Assertion Reference

The following sections provide SALT WS-AT Assertion reference information:

- Overview
- Policy File Example

4.1 Overview

WS-AT defines a policy assertion that allows requests to indicate whether an operation call *must* or *may* be made as part of an Atomic Transaction. For the configuration impact of Atomic Transaction policy assertions, see the "Configuration Changes" chapter.

Depending on the direction of the calls and meaning of the policy assertion setting, the runtime inbound/outbound transaction behavior is as follows:

- Inbound Transactions
 For inbound transactions, there are no particular runtime behavior changes. The client consuming the WSDL accepts transactions based on the configured value. Runtime behavior is normal.
- Outbound Transactions
 - If an ATAssertion element without "Optional=true" is configured for a service, the call
 has to be made in a transaction. If no corresponding XA transaction exists at the time,
 the WS-TX transaction is initiated (but not associated with any Oracle Tuxedo XA
 transactions). If an XA transaction exists, there is no change in behavior.
 - If an ATAssertion element with "Optional=true" is configured for a service, an
 outbound transaction context is requested *only* if a corresponding Oracle Tuxedo XA
 transaction exists in the context of the call.
 - If no ATAssertion element is configured for a service, the corresponding service call is made outside of any transaction. When a call is made to an external Web Service in the context of an Oracle Tuxedo XA transaction, the Web Service call does not propagate the transaction. This allows excluding certain Web Service calls from a global transaction, and represents the default for most existing Web Services calls that do not support WS-TX.

4.2 Policy File Example

The existing policy file mechanism includes the addition of WS-AT policy elements.WS-AT defines the ATAssertion element, with an Optional attribute, as follows:

```
/wsat:ATAssertion/@wsp:Optional="true"
```

The following example shows policy.xml file with an ATAssertion element.

Example 4-1 policy.xml File with an ATAssertion Element

```
<?xml version="1.0"?>
<wsp:Policy wsp:Name="TransactionalServicePolicy"</pre>
```



xmlns:wsp="http://schemas.xmlsoap.org/ws/2004/09/policy"
xmlns:wsat="http://docs.oasis-open.org/ws-tx/wsat/2006/06">
 <wsat:ATAssertion wsp:Optional="true"/>
</wsp:Policy>

SALT WS-ReliableMessaging Policy Assertion Reference

The following sections provide SALT WS-ReliableMessaging (WS-RM) Policy Assertion reference information:

- Overview
- WS-RM Policy Assertion Format
- WS-RM Assertion File Example
- WS-RM Assertion Element Description

5.1 Overview

SALT provides support for WS-ReliableMessaging (WS-ReliableMessaging 1.0, Feb., 2005 specification), which allows two Web Service applications running on different GWWS instances to communicate reliably in the event of software component, system, or networks failure.

A WS-Policy file containing WS-ReliableMessaging Policy Assertion is used to configure the reliable messaging capabilities of a GWWS server on a destination endpoint. SALT supports the WS-ReliableMessaging Policy Assertion specification to ensure the interoperability with Oracle WebLogic 9.x / 10.


For more information, see Configuring Advanced Web Service Messaging Features in the SALT Configuration Guide

5.2 WS-RM Policy Assertion Format

The following figure shows a graphical representation of the WS-ReliableMessaging Policy Assertion format in a WS-Policy file:



Figure 5-1 WS-ReliableMessaging Policy Assertion Formating



5.3 WS-RM Assertion File Example

The following example shows a sample WS-Policy file that contains WS-RM policy assertion.

Example 5-1 Sample WS-ReliableMessaging Policy Assertion File

```
<?xml version="1.0"?>
<wsp:Policy wsp:Name="ReliableSomeServicePolicy"
  xmlns:wsrm="http://schemas.xmlsoap.org/ws/2005/02/rm"
  xmlns:wsp="http://schemas.xmlsoap.org/ws/2004/09/policy"
  xmlns:beapolicy="http://www.bea.com/wsrm/policy">
  <wsrm:RMAssertion>
    <wsrm:InactivityTimeout Milliseconds="600000" />
    <wsrm:BaseRetransmissionInterval Milliseconds="500"/>
    <wsrm:ExponentialBackoff />
    <wsrm:AcknowledgementInterval Milliseconds="2000" />
    <beapolicy:Expires Expires="PlD" />
    <beapolicy:QOS QOS="ExactlyOnce InOrder" />
    </wsrm:RMAssertion>
</wsp:Policy>
```

5.4 WS-RM Assertion Element Description

All RM assertions are optional, and if not specified, the default value are used. The following definitions describe the RM assertion options.

- <wsrm:InactivityTimeout>
- <wsrm:AcknowledgmentInterval>
- <wsrm:BaseRetransmissionInterval>
- <wsrm:ExponentialBackoff>



- <beapolicy:Expires>
- <beapolicy:QOS>
- <wsrm:RMAssertion>

5.4.1 <wsrm:InactivityTimeout>

Specifies the number of milliseconds, specified with the Milliseconds attribute, which defines an inactivity interval. After time has elapsed, if the destination endpoint has not received a message from the source endpoint, the destination endpoint may terminate current sequence due to inactivity. The source endpoint can also use this parameter.

Sequences never time out by default.

5.4.2 <wsrm:AcknowledgmentInterval>

Specifies the maximum interval, in milliseconds, in which the destination endpoint must transmit a stand-alone acknowledgment.

This element is optional. If this element is not specified, There is no time limit by default.

5.4.3 <wsrm:BaseRetransmissionInterval>

Specifies the interval, in milliseconds, that the source endpoint waits after transmitting a message and before it retransmits the message if it receives no acknowledgment for that message. This value will apply to the GWWS server when it sends a response in an outbound sequence.

The default value is 20000 milliseconds.

5.4.4 <wsrm:ExponentialBackoff>

Specifies that the retransmission interval is adjusted using the exponential back off algorithm. This value applies to the GWWS server when it sends a response in an outbound sequence.

5.4.5 <beapolicy:Expires>

Specifies the amount of time after which the reliable Web service expires and does not accept any new sequence messages.

This element has a single attribute, Expires, whose data type is an XML Schema duration type. For example, if you want to set the expiration time to one day, use the following:

```
< beapolicy:Expires Expires="P1D" />
```

The default value never expires.

5.4.6 <beapolicy:QOS>

Specifies the delivery assurance. SALT supports the following assurances:

- AtMostOnce Messages are delivered at most once, without duplication. There is possibility that some messages may not be delivered.
- AtLeastOnce Every message is delivered at least once. There is possibility that some messages are delivered more than once.



- ExactlyOnce Each message is delivered exactly once, without duplication.
- InOrder Messages are delivered in the order that they were sent. This delivery assurance can be combined with one of the preceding three assurances.

The default value is "ExactlyOnce InOrder".

5.4.7 <wsrm:RMAssertion>

Main WS-RM assertion that groups all the other assertions under a single element.

The presence of this assertion in a WS-Policy file indicates that the corresponding Web Service application must be invoked reliably.

SALT WS-SecurityPolicy Assertion 1.2 Reference

The following sections provide SALT WSSP1.2 reference information:

- Overview
- SALT WSSP 1.2 Policy File Examples
- SALT WSSP 1.2 Policy Templates
- SALT WSSP1.2 Assertion Description

6.1 Overview

SALT implements part of WS-Security protocol version 1.1 for inbound services. Authentication with UsernameToken and X509v3Token are supported. To describe how the authentication is carried out, WS-SecurityPolicy is used in WSDL definition.

In order to communicate with Oracle WebLogic Release 10 via WS-Security 1.1, SALT implements the counterparts of WS-SecurityPolicy (WSSP) 1.2 supported by WebLogic 10. But the supported WSSP 1.2 assertions are limited as follows:

- Protection Assertions
 - Integrity Assertion
 - <u><sp:SignedParts></u> Assertion (Limited support)
- Token Assertions:
 - <sp:UsernameToken> Assertion (Limited support)
 - <sp:X509Token> Assertion (Limited support)
- Security Binding Assertions:
 - AsysmmetricBinding Assertion (Limited support)
 - <u><sp:TransportBinding</u> > Assertion (Limited support)
- Supporting Tokens Assertions:
 - SupportingTokens Assertion (Limited support)

For more details about limitations of WS-SecurityPolicy 1.2 assertions, please refer to <u>Oracle SALT WSSP1.2 Assertion Description</u>.

For more information about WSSP 1.2 assertions supported by WebLogic 10, please refer to in the Oracle WebLogic Web Services Documentation <u>Oracle Web Services Security Policy</u>
Assertion Reference

In this document, XML namespace prefix "sp" stands for namespace URI "http://docs.oasis-open.org/ws-sx/ws-securitypolicy/200512".



6.2 SALT WSSP 1.2 Policy File Examples

This section contains the following topics:

- WSSP 1.2 Policy File Sample
- Wssp1.2-Wss1.0-X509.xml File Sample

6.2.1 WSSP 1.2 Policy File Sample

Following is an example of Username token authentication with WSSP 1.2 assertions.

Example 6-1 WSSP 1.2 Policy File Sample

```
<!-Binding Policy -->
<wsp:Policy</pre>
  xmlns:wsp="http://schemas.xmlsoap.org/ws/2004/09/policy"
 xmlns:sp="http://docs.oasis-open.org/ws-sx/ws-securitypolicy/200512">
  <sp:TransportBinding>
    <wsp:Policy>
      <sp:TransportToken>
        <wsp:Policy>
          <sp:HttpToken/>
        </wsp:Policy>
      </sp:TransportToken>
      <sp:AlgorithmSuite>
        <wsp:Policy>
          <sp:Basic256/>
        </wsp:Policy>
      </sp:AlgorithmSuite>
      <sp:Layout>
        <wsp:Policy>
          <sp:Lax/>
        </wsp:Policy>
      </sp:Layout>
      <sp:IncludeTimestamp/>
    </wsp:Policy>
  </sp:TransportBinding>
  <sp:SupportingTokens>
    <wsp:Policy>
      <sp:UsernameToken
          sp:IncludeToken="http://docs.oasis-open.org/ws-sx/ws-securitypolicy/
200512/IncludeToken/AlwaysToRecipient">
        <wsp:Policy>
          <sp:WssUsernameToken10/>
        </wsp:Policy>
      </sp:UsernameToken>
    </wsp:Policy>
  </sp:SupportingTokens>
</wsp:Policy>
```



6.2.2 Wssp1.2-Wss1.0-X509.xml File Sample

Example 6-2 Wssp1.2-Wss1.0-X509.xml File Sample

```
<?xml version="1.0"?>
<wsp:Policy</pre>
xmlns:wsp="http://schemas.xmlsoap.org/ws/2004/09/policy"
xmlns:sp="http://docs.oasis-open.org/ws-sx/ws-securitypolicy/200512"
  <sp:AsymmetricBinding>
    <wsp:Policy>
      <sp:InitiatorToken>
        <wsp:Policy>
          <sp:X509Token
sp:IncludeToken="http://docs.oasis-open.org/ws-sx/ws-securitypolicy/200512
/IncludeToken/AlwaysToRecipient">
            <wsp:Policy>
              <sp:WssX509V3Token10/>
            </wsp:Policy>
          </sp:X509Token>
        </wsp:Policy>
      </sp:InitiatorToken>
      <sp:Layout>
        <wsp:Policy>
          <sp:Lax/>
        </wsp:Policy>
      </sp:Layout>
      <sp:OnlySignEntireHeadersAndBody/>
    </wsp:Policy>
  </sp:AsymmetricBinding>
  <sp:SignedParts>
    <sp:Body/>
  </sp:SignedPart>
```

6.3 SALT WSSP 1.2 Policy Templates

SALT provides a number of WS-SecurityPolicy 1.2 template files you can use for most typical Web Service applications. These policy files are located in directory TUXDIR/udataobj/salt/policy.

Table 6-1 WSSP 1.2 Policy Template Files

Policy File	Description
wssp1.2-UsernameToken-plain-auth.xml	Username token with plain text password is sent in the request for authentication.
wssp1.2-x509v3-auth.xml	X509 V3 binary token (certificate) is sent in the request for authentication. The request is optionally signed with some message parts in the requests.
wssp1.2-signbody.xml	The entire SOAP body is signed.

These template files can be referenced directly in the WSDF files with location value format:



salt:<template_file_name>

For example, if you want to configure signbody, you can specify the followings in your WSDF file:

<Policy location="salt:wssp1.2-signbody.xml" />

6.4 SALT WSSP1.2 Assertion Description

Below are all SALT supported WSSP 1.2 assertions and limitations for each one. Customers should obey the limitation when writing their own customized WSSP 1.2 policy files. SALT does not check any customized WSSP 1.2 policy file against the limitation rules. If something claimed in the customized WSSP 1.2 policy file cannot be supported by SALT, web service client program may result run time errors.

WS-SecurityPolicy 1.2 assertions not listed below are definitely not supported by SALT.

- <sp:SignedParts>
- <sp:UsernameToken>
- <sp:X509Token>
- <sp:AlgorithmSuite>
- <sp:Layout>
- <sp:TransportBinding >
- <sp:AsymmetricBinding>
- <sp:SupportingToken>

6.4.1 <sp:SignedParts>

Specifies the parts of a SOAP message to be digitally signed. SALT only supports the entire SOAP body to be signed.

Limitations

6.4.1.1 Limitations

- Child element <sp:Body> is supported for configuring the entire SOAP body to be signed.
- Child element <sp:Header> is not yet supported.
- No nesting WSSP 1.2 assertion for this assertion.

6.4.2 <sp:UsernameToken>

Specifies username token to be included in the SOAP message. SALT only supports username token with clear text password defined in WS-Security Username Token Profile 1.0. <UsernameToken> assertion must be used as a nested assertion of Security Binding Assertions and Supporting Token Assertions.

• Limitations

6.4.2.1 Limitations

Supported Nesting Assertions



- <sp:WssUsernameToken10>
- Not yet supported Nesting Assertions
 - <sp:WssUsernameToken11>
 - <sp:NoPassword>
 - <sp:HashPassword>

6.4.3 <sp:X509Token>

Specifies a binary security token carrying an X509 token to be included in the SOAP message. <X509Token> assertion must be used as a nested assertion of Security Binding Assertions and Supporting Token Assertions.

Limitations

6.4.3.1 Limitations

- Supported Nesting Assertions
 - <sp:WssX509V3Token10>
 - <sp:WssX509V3Token11>
- Non-Supported Nesting Assertions
 - <sp:WssX509Pkcs7Token10>
 - <sp:WssX509Pkcs7Token11>
 - <sp:WssX509PkiPathV1Token10>
 - <sp:WssX509PkiPathV1Token11>
 - <sp:WssX509V1Token10>
 - <sp:WssX509V1Token11>

6.4.4 <sp:AlgorithmSuite>

Specifies the algorithm suite to be used for performing cryptographic operations with security tokens. <AlgorithmSuite> Assertion must be used as a nested assertion of Security Binding Assertions.

Limitations

6.4.4.1 Limitations

- Supported Nesting Algorithm Suite
 - <sp:Basic256>
- Non-Supported Nesting Algorithm Suites
 - All the other Algorithm Suite listed in the WS-Security Policy 1.2 specification.

6.4.5 <sp:Layout>

Specifies the layout rules when adding items to the security header. <Layout> Assertion must be used as a nested assertion of Security Binding Assertions.



Limitations

6.4.5.1 Limitations

- Supported Nesting Layout rules
 - <sp:Lax>
- Non-Supported Nesting Layout rules
 - <sp:Strict>
 - <sp:LaxTimestampFirst>
 - <sp:LaxTimestampLast>

6.4.6 <sp:TransportBinding >

Specifies the message protection and security correlation is provided using the means of the transport. The <TransportBinding> token is used mainly for carrying isolated Username Token in the SOAP message.

Limitations

6.4.6.1 Limitations

- Supported Nesting Assertions
 - <sp:TransportToken>
 - <sp:AlgorithmSuite>
 - <sp:Layout>
 - <sp:IncludeTimestamp>
- Nesting Assertion <sp:TransportToken> only supports <sp:HttpToken>

The following example shows a SALT supported TransportToken Assertion:

Example 6-3 Supported TransportToken Assertions



6.4.7 <sp:AsymmetricBinding>

Specifies the message protection is provided by means defined in WS-Security SOAP Message Security, and the request and response message can use distinct keys for encryption and signature, because of their different lifecycles. The <AsymmetricBinding> Assertion is used mainly for carrying X.509 binary security token in the SOAP request messages for inbound calls.

Limitations

6.4.7.1 Limitations

- Supported Nesting Assertions
 - <sp:InitiatorToken>
 - <sp:RecipientToken>
 - <sp:AlgorithmSuite>
 - <sp:Layout>
 - <sp:IncludeTimestamp>
 - <sp:ProtectTokens>
 - <sp:OnlySignEntireHeadersAndBody>
- Non-supported Nesting Assertions
 - <sp:InitiatorSignatureToken>
 - <sp:InitiatorEncryptToken>
 - <sp:RecipientSignatureToken>
 - <sp:RecipientEncryptToken>
 - <sp:EncryptBeforeSigning>
 - <sp:EncryptSignature>
- <sp:InitiatorToken> must be associated <sp:X509Token> and the Token inclusion type must be "AlwaysToRecipient"
- <sp:RecipientToken> must be associated with <sp:X509Token> and the Token inclusion type must be "Never"

The following example shows a SALT supported AsymmetricBinding assertion example. This assertion indicates the X.509 V3 binary token that defined in WS-Security X.509 Token Profile 1.1 specification is used for digital signature for the SOAP request messages and the X.509 token is always included in the SOAP message security header:

Example 6-4 Supported AsymmetricBinding Assertion



```
</wsp:Policy>
          </sp:X509Token>
        </wsp:Policy>
      </sp:InitiatorToken>
      <sp:RecipientToken>
        <wsp:Policy>
          <sp:X509Token
                                       sp:IncludeToken="http://docs.oasis-
open.org/ws-sx/ws-securitypolicy/200512/IncludeToken/Never">
            <wsp:Policy>
              <sp:WssX509V3Token11 />
            </wsp:Policy>
          </sp:X509Token>
        </wsp:Policy>
      </sp:RecipientToken>
      <sp:Algorithm>
        <wsp:Policy>
          <sp:Basic256>
        </wsp:Policy>
      </sp:Algorithm>
      <sp:Layout>
        <wsp:Policy>
          <sp:Lax>
        </wsp:Policy>
      </sp:Layout>
      <sp:IncludeTimestamp />
    </wsp:Policy>
  </sp:AsymmetricBinding>
```

6.4.8 <sp:SupportingToken>

Specifies security tokens that are included in the security header and may optionally include additional message parts to sign and/or encrypt. For SALT, <SupportingToken> Assertion is used mainly to include Username Token in the security header when <sp:AsymmetricBinding> Assertion is used.

For more information, see <sp:AsymmetricBinding>

Limitations

6.4.8.1 Limitations

- Supported Nesting Assertions
 - <sp:UsernameToken>
 - <sp:X509Token>
- Not-non Supported Nesting Assertions
 - <sp:SignedParts>
 - <sp:SignedElements>
 - <sp:EncryptedParts>
 - <sp:EncryptedElements>
- All supported token assertions must be defined with Token inclusion type "AlwaysToRecipient"



The following example shows a SALT supported SupportingToken assertion. This assertion indicates the Username token is always included in SOAP request messages:

Example 6-5 Supported SupportingToken Assertion

SALT WS-SecurityPolicy Assertion 1.0 Reference

The following sections provide SALT WS-SecurityPolicy (WSSP) 1.0 assertion reference information:

- Overview
- SALT WSSP 1.0 Policy Assertion Format
- SALT WSSP 1.0 Assertion File Example
- SALT WSSP 1.0 Policy Templates
- SALT WSSP 1.0 Assertion Element Description

7.1 Overview

SALT implements part of WS-Security protocol version 1.0 for inbound services. Authentication with UsernameToken and X509v3Token are supported. WS-SecurityPolicy 1.0 assertions are used in WSDL definition to describe how the authentication is carried out. The WS-SecurityPolicy1.0 specification (2002) is supported in order to ensure the interoperability with Oracle WebLogic 9.x.

Below are all SALT supported WS-SecurityPolicy 1.0 assertions:

- SecurityToken Assertions:
 - UsernameToken Assertion and X509Token Assertion
- Integrity Assertion
- Identity Assertion

There are some extension assertions used in WebLogic 9.x, SALT only implements a subset of them. Integrity Assertion is only used when using X509v3 token for authentication. And the only message part can be specified for signature is the whole SOAP Body.

7.2 SALT WSSP 1.0 Policy Assertion Format

The following figure shows a graphical representation of the SALT supported WS-SecurityPolicy 1.0 Assertion format in a WS-Policy file.



<wsp:Policy> No annotation: Exactly one <ld><ldentity> ?</ld> *: Zero or more +: One or more <SupportedTokens>? ?: Zero or one <SecurityToken> + <Claims> ? <UsePassword>? <Integrity>? <SignatureAlgorithm> <CanonicalizationAlgorithm> <SupportedTokens>? <SecurityToken> + <Target> + <DigestAlgorithm> <Transform> *

Figure 7-1 SALT Supported WS-SecurityPolicy 1.0 Assertion Format

7.3 SALT WSSP 1.0 Assertion File Example

The following example demonstrates how to apply Username token authentication with WSSP 1.0 Assertions:

<MessageParts>

Example 7-1 WSSP 1.0 Policy File Sample

```
<wsp:Policy xmlns:wsp="http://schemas.xmlsoap.org/ws/2004/09/policy"</pre>
    xmlns:wssp="http://www.bea.com/WLS/security/policy"
    xmlns:wsu="http://docs.oasis-open.org/wss/2004/01/oasis-200401-wss-wssec
urity-utility-1.0.xsd">
    <wssp:Identity>
        <wssp:SupportedTokens>
            <wssp:SecurityToken</pre>
                TokenType="http://docs.oasis-open.org/wss/2004/01/oasis-200401
-wss-username-token-profile-1.0#UsernameToken">
                <wssp:Claims>
            <wssp:UsePassword>http://docs.oasis-open.org/wss/2004/01/oasis-2
00401-wss-username-token-profile-1.0#PasswordText</wssp:UsePassword>
                </wssp:Claims>
            </wssp:SecurityToken>
        </wssp:SupportedTokens>
    </wssp:Identity>
</wsp:Policy>
```



7.4 SALT WSSP 1.0 Policy Templates

SALT provides a number of WS-SecurityPolicy 1.0 template files you can use for most typical Web Service applications. These policy files are located in directory TUXDIR/udataobj/salt/policy.

Table 7-1 SALT WSSP 1.0 Policy Template Files

Policy File	Description
wssp1.0-UsernameToken-plain-auth.xml	Username token with plain text password is sent in the request for authentication.
wssp1.0-x509v3-auth.xml	X509 V3 binary token (certificate) is sent in the request for authentication. The request is optionally signed with some message parts in the requests.
wssp1.0-signbody.xml	The whole SOAP body is signed.

These template files can be referenced directly in the WSDF files with location value format:

salt:<template_file_name>

For instance, if you want to configure signbody, you can specify the followings in your WSDF file:

<Policy location="salt:wssp1.0-signbody.xml" />

7.5 SALT WSSP 1.0 Assertion Element Description

SALT implements part of WebLogic 12.x / 10 WS-SecurityPolicy 1.0 assertions. For a complete list of WSSP 1.0 assertions supported by WebLogic, see http://docs.oracle.com/middleware/ 1212/wls/WSREF/sec_assert.htm#g1077013

- <CanonicalizationAlgorithm>
- <Claims>
- <DigestAlgorithm>
- <ldentity>
- <Integrity>
- <MessageParts>
- <SecurityToken>
- <SignatureAlgorithm>
- <SupportedTokens>
- <Target>
- <Transform>
- <UsePassword>
- Usage of MessageParts



7.5.1 < Canonicalization Algorithm>

Specifies the algorithm used to canonicalize the SOAP message elements that are digitally signed.

Table 7-2 CanonicalizationAlgorithm Attribute

Attribute	Description	Required?
URI	The algorithm used to canonicalize the SOAP message being signed. SALT supports only the following canonicalization algorithm: W3C	Yes

7.5.2 < Claims >

Specifies additional metadata information that is associated with a particular type of security token. Depending on the type of security token, you must specify the following child elements:

 For username tokens, you must specify a <<u>UsePassword></u> child element to specify what kind of the password will be used for in username authentication.

This element does not have any attributes.

7.5.3 < Digest Algorithm >

Specifies the digest algorithm that is used when digitally signing the specified parts of a SOAP message. Use the $\underline{\text{MessageParts}}$ sibling element to specify the parts of the SOAP message you want to digitally sign.

Table 7-3 DigestAlgorithm Attributes

Attribute	Description	Required?
URI	The digest algorithm that is used when digitally signing the specified parts of a SOAP message. SALT supports only the following digest algorithm:	Yes
	http://www.w3.org/2000/09/ xmldsig#sha1	

7.5.4 < Identity>

Specifies the type of security tokens (username or X.509) that are supported for authentication.

This element has no attributes.



7.5.5 < Integrity >

Specifies that part or all of the SOAP message must be digitally signed, as well as the algorithms and keys that are used to sign the SOAP message.

For example, a Web Service may require that the entire body of the SOAP message must be digitally signed and only algorithms using SHA1 and an RSA key are accepted.

Table 7-4 Integrity Attributes

Attribute	Description	Required?
SignToken	Specifies whether the security token, specified using the <securitytoken> child element of <integrity>, should also be digitally signed, in addition to the specified parts of the SOAP message. The valid values for this attribute are true and false. The default values is true.</integrity></securitytoken>	No

7.5.6 < Message Parts >

Specifies the parts of the SOAP message that should be signed. SALT only supports certain pre-defined message part function, wsp:Body(), that is. the entire SOAP body to be digitally signed.

The MessageParts assertion is always a child of a <a href

See <u>Usage of MessageParts</u> for more information about how to specify the parts of the SOAP message that should be signed.

Table 7-5 MessageParts Attributes

Attribute	Description	Required?
Dialect	Identifies the dialect used to identity the parts of the SOAP message that should be signed. SALT only supports the following value:	Yes
	http://schemas.xmlsoap.org/ 2002/12/wsse#part	
	Convenience dialect used to specify parts of SOAP message that should be signed.	

7.5.7 < Security Token >

Specifies the security token that is supported for authentication or digital signatures, depending on the parent element.



If this element is defined in the <<u>Identity</u> parent element, then is specifies that a client application, when invoking the Web Service, must attach a security token to the SOAP request. For example, a Web Service might require that the client application present a Username token for the Web Service to be able to access Tuxedo service. If this element is part of <<u>Integrity</u>, then it specifies the token used for digital signature.

The specific type of the security token is determined by the value of its TokenType attribute, as well as its parent element.

Table 7-6 SecurityToken Attributes

Attribute	Description	Required
IncludeInMessage	Specifies whether to include the token in the SOAP message. Valid values are true or false.	No
	The default value of this attribute is true when used in the Integrity assertion.	
	The value of this attribute is always true when used in the Lidentity> assertion, even if you explicitly set it to false.	
TokenType	Specifies the type of security token. Valid values are: • http://docs.oasis- open.org/wss/2004/01/ oasis-200401-wss-x509- token-profile-1.0#X509v3 (To specify a binary X.509 v3 token) • http://docs.oasis- open.org/wss/2004/01/ oasis-200401-wss- username-token- profile-1.0#UsernameToken (To specify a username token)	Yes

7.5.8 < Signature Algorithm >

Specifies the cryptographic algorithm used to compute the digital signature.



Table 7-7 Signature Algorithm Attributes

Attribute	Description	Required?
URI	Specifies the cryptographic algorithm used to compute the signature.	Yes
	Be sure that you speci fy an algor ithm that is com patibl e with the certificates you are using in your enter prise .	
	Valid values are: http://www.w3.org/2000/09/xmldsig#rsa-sha1 http://www.w3.org/2000/09/xmldsig#dsa-sha1	

7.5.9 < Supported Tokens >

Specifies the list of supported security tokens that can be used for authentication, or digital signatures, depending on the parent element.

This element has no attributes.

7.5.10 < Target >

Encapsulates information about which targets of a SOAP message are to be signed. When used in Integrity>, you can specify the DigestAlgorithm>, Transform>, and MessageParts> child elements.



Ideally, you can have one or more targets. But at most one target is enough for SALT, since SALT only supports the entire SOAP body to be configured for digital signature.

This element has no attributes.

7.5.11 <Transform>

Specifies the URI of a transformation algorithm that is applied to the parts of the SOAP message that are signed. Only can exist in a child element of the <Integrity> element.

You can specify zero or more transforms, which are executed in the order they appear in the <Target> parent element.

Table 7-8 Transform Attributes

Attribute	Description	Required?
URI	Specifies the URI of the transformation algorithm. SALT only supports the following transformation algorithm:	Yes
	http://www.w3.org/2000/09/ xmldsig#base64 (Base64 decoding transforms)	
	For detailed information about these transform algorithms, see XML-Signature Syntax and Processing.	

7.5.12 <UsePassword>

Specifies that whether the plain text or the digest of the password appear in the SOAP messages. This element is used only with username tokens. In SALT, it must be specified as plain text.



Table 7-9 UsePassword Attributes

Attribute	Description	Required?
Type Type	Description Specifies the type of password. SALT only supports cleartext passwords, the value URI is: http://docs.oasis-open.org/wss/2004/01/oasis-200401-wss-username-token-profile-1.0#PasswordText Specifies that cleartext passwords should be used in the SOAP messages.	Required? Yes
	For back ward com patibility reas ons, the precedin gullican also be specified with an initial "www." For exam ple: http://www.docs.oasis - open .org/wss/2004/01/oasis -200	



Table 7-9 (Cont.) UsePassword Attributes

Attribute	Description	Required?
	401- wss- user nam e- token - profil e-1.0 #Pas swor dText	

7.5.13 Usage of MessageParts

When you use the Integrity assertion in your WS-Policy file, you are required to also use the Target child assertion to specify the targets of the SOAP message to digitally sign. The Integrity assertion in turn requires that you use the Integrity assertion in turn requires that you use the Integrity assertion in turn requires that you use the Integrity assertion to specify the actual parts of the SOAP message that should be digitally signed. You can use the Dialect attribute of Integrity assertion in turn requires that you use the Integrity assertion in turn requires that you use the Integrity assertion in turn requires that you use the Integrity assertion in turn requires that you use the Integrity assertion in turn requires that you use the Integrity assertion in turn requires that you use the Integrity assertion in turn requires that you use the Integrity assertion in turn requires that you use the Integrity assertion in turn requires that you use the Integrity assertion in turn requires that you use the Integrity assertion in turn requires that you use the Integrity assertion in turn requires that you use the Integrity assertion in turn requires that you use the Integrity assertion in turn requires that you use the Integrity assertion in turn requires that you use the Integrity assertion in turn requires that you use the Integrity assertion in turn requires that you use the Integrity assertion in turn requires that you use

Pre-Defined Message Part Selection Function

Be sure that you specify a message part that actually exists in the SOAP messages that result from a client invoke of a message-secured Web Service. If the Web Services security module encounters an inbound SOAP message that does not include a part that the WS-Policy file indicates should be signed or encrypted, then the Web Services security module returns an error and the invoke fails.

• Pre-Defined Message Part Selection Function

7.5.13.1 Pre-Defined Message Part Selection Function

This section shows SALT supported functions that are used with the "http://schemas.xmlsoap.org/2002/12/wsse#part" dialect for selecting parts of a message:

Table 7-10 SALT Supported Message Part Selection Function

Function	Description
wsp:Body()	Specifies the entire SOAP message body to be selected as one part

You can only specify the entire SOAP body to be signed. It is recommended that you use the dialect that pre-defines the wsp:Body() function for this purpose.

The following example shows a wsp:Body() function



Example 7-2 wsp:Body() Function

<wssp:MessageParts
 Dialect="http://schemas.xmlsoap.org/2002/12/wsse#part">
 wsp:Body()
</wssp:MessageParts>