

Oracle® Communications Billing and Revenue Management

PDC Installation Guide



Release 15.0
F86196-01
December 2023

The Oracle logo, consisting of a solid red square with the word "ORACLE" in white, uppercase, sans-serif font centered within it.

ORACLE®

Copyright © 2017, 2023, Oracle and/or its affiliates.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software, software documentation, data (as defined in the Federal Acquisition Regulation), or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs) and Oracle computer documentation or other Oracle data delivered to or accessed by U.S. Government end users are "commercial computer software," "commercial computer software documentation," or "limited rights data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, reproduction, duplication, release, display, disclosure, modification, preparation of derivative works, and/or adaptation of i) Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs), ii) Oracle computer documentation and/or iii) other Oracle data, is subject to the rights and limitations specified in the license contained in the applicable contract. The terms governing the U.S. Government's use of Oracle cloud services are defined by the applicable contract for such services. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle®, Java, MySQL and NetSuite are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Inside are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Epyc, and the AMD logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

Contents

Preface

Audience	viii
Documentation Accessibility	viii
Diversity and Inclusion	viii

Part I Getting Started

1 Pricing Design Center Installation Overview

Overview of the PDC Installation Procedure	1-1
Overview of the PDC Upgrade Procedure	1-1
Ensuring a Successful PDC Installation	1-2

2 Pricing Design Center System Requirements

Software Requirements	2-1
Hardware Requirements	2-1
Information Requirements	2-1
Pricing Design Center WebLogic Server Connection Information	2-2
PDC Database Connection Information	2-2
PDC Schema Information	2-3
BRM Server Information	2-3
BRM Pipeline Manager Database Information	2-3
Transformation Cross-Reference Database Information	2-4
Transformation Cross-Reference Schema Information	2-5
Migration Cross-Reference Database Information	2-5
Migration Cross-Reference Schema Information	2-6

Part II Installing Pricing Design Center

3 Pricing Design Center Preinstallation Tasks

Preinstallation Tasks for Installing the PDC Software for the First Time	3-1
Installing and Configuring Oracle Database	3-1
Setting the Database Time Zone	3-2
Tuning the Database	3-2
Configuring SSL for the PDC Database	3-3
Installing JRE/JDK	3-3
Installing and Configuring Oracle WebLogic Server	3-3
Downloading and Installing Oracle WebLogic Server	3-4
Copying Library JAR Files for PDC Installation	3-4
Applying WebLogic Server Patch	3-5
Installing Oracle Application Development Runtime	3-5
Creating the Oracle WebLogic Server Domain	3-6
Configuring SSL for the WebLogic Server Domain	3-7
Configuring the SSL Protocol Version	3-8
Setting the JDBC Path for the WebLogic Server Domain	3-8
Configuring WebLogic Server to use SSL-Enabled Data Source	3-9
Updating JDBC LLR Table Name	3-9
Setting the JAVA_HOME Environment Variable	3-9
Enabling JRE Permissions	3-10
Enabling BRM-PDC Integration	3-10

4 Installing Pricing Design Center

About the PDC Installer and PDC Schema	4-1
About Installing PDC	4-1
Downloading the PDC Software	4-2
Installing PDC in GUI Mode	4-2
Installing All PDC Components	4-2
Installing Only the PDC Software	4-17
Installing Only BRM Integration Pack	4-24
Installing Only PDC REST Services Manager	4-35
Installing PDC in Silent Mode	4-37
Creating a Response File	4-37
Installing PDC in Silent Mode	4-38
About Installation Logs	4-38

5 Pricing Design Center Postinstallation Tasks

Postinstallation Tasks for the PDC Installation	5-1
Creating a PDC User	5-2

Adding the PDC User to a Group	5-3
Starting the Transformation Engines	5-3
Restricting Tablespace Quota for a Schema User	5-4
Configuring WebLogic Server to use SSL-Enabled Data Source	5-5
Configuring PDC to Connect to SSL-Enabled Database	5-5
Cleaning up Sample BRM Data	5-6
Running SyncPDC	5-8
Loading Sample Data	5-8
Creating Service-Event Maps	5-9
Configuring Mapping of TMF620 priceType to BRM Event Names	5-10
Updating the Base URL for PDC REST Services Manager	5-10

Part III Upgrading Pricing Design Center from 12.x to 15.0

6 Pricing Design Center Pre-Upgrade Tasks

Preinstallation Tasks for the PDC Software Upgrade	6-1
Shutting Down the Current Instance	6-2
Backing Up the Current Installation	6-2
Installing JRE/JDK	6-3
Configuring SSL for the PDC Database	6-3
Downloading and Installing Oracle WebLogic Server	6-3
Copying Library JARs for PDC Upgrades	6-3
Configuring WebLogic Server to use SSL-Enabled Data Source	6-4
Updating JDBC LLR Table Name	6-4
Setting the JAVA_HOME Environment Variable	6-5
Enabling JRE Permissions	6-5
Installing Oracle Application Development Runtime	6-6
Enabling the SSL Port for the WebLogic Server Domain	6-6
Configuring the SSL Protocol Version	6-7

7 Upgrading Pricing Design Center Software

About Upgrading PDC	7-1
Upgrading PDC in GUI Mode	7-1
Upgrading Both PDC and BRM Integration Pack	7-1
Upgrading Only the PDC Software	7-10
Upgrading Only BRM Integration Pack	7-15
Upgrading PDC in Silent Mode	7-21
Creating a Response File	7-21
Upgrading PDC and BRM Integration Pack in Silent Mode	7-22

8 Pricing Design Center Post-Upgrade Tasks

Post-Upgrade Tasks for PDC	8-1
Upgrading the PDC Database Schema	8-2
Migrating Offer Profiles from BRM into PDC	8-2
Starting the Transformation Engines	8-4
Running the BRM Integration Pack Upgrade Script	8-4
Restricting Tablespace Quota for a Schema User	8-6
Configuring WebLogic Server to use SSL-Enabled Data Source	8-6
Configuring PDC to Connect to SSL-Enabled Database	8-7
Running SyncPDC	8-8

Part IV Setting Up SSO for PDC

9 Setting Up Single Sign-On for Pricing Design Center

About Setting Up SSO for PDC	9-1
Creating a SAML Assertion Provider	9-1
Creating a SAML Authenticator	9-2
Performing SAML 2.0 General Configurations	9-3
Configuring the SAML Service Provider	9-3
Publishing the Service Provider Metadata	9-4
Updating the Deployment Plan for PDC	9-4

Part V Verifying Pricing Design Center

10 Verifying the Pricing Design Center Installation

Verifying the PDC Installation	10-1
Verifying the BRM Integration Pack Installation	10-2
Verifying the PDC REST Services Manager Installation	10-2

Part VI Uninstalling Pricing Design Center

11 Uninstalling Pricing Design Center

Uninstalling PDC in GUI Mode	11-1
Uninstalling BRM Integration Pack in GUI Mode	11-2

Uninstalling PDC REST Services Manager in GUI Mode	11-3
Uninstalling PDC Using the Silent Mode	11-4
Uninstalling BRM Integration Pack Using the Silent Mode	11-4
Uninstalling PDC REST Services Manager Using the Silent Mode	11-5

Preface

This guide provides instructions for installing and administering Oracle Communications Pricing Design Center (PDC).

Audience

This document is intended for system administrators, database administrators, and developers who install and configure PDC.

Before reading this guide, you should have familiarity with PDC. See *PDC Creating Product Offerings* for more information.

PDC requires Oracle Database and Oracle WebLogic Server. See the documentation for those products for installation and configuration instructions.

Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc>.

Access to Oracle Support

Oracle customers that have purchased support have access to electronic support through My Oracle Support. For information, visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info> or visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs> if you are hearing impaired.

Diversity and Inclusion

Oracle is fully committed to diversity and inclusion. Oracle respects and values having a diverse workforce that increases thought leadership and innovation. As part of our initiative to build a more inclusive culture that positively impacts our employees, customers, and partners, we are working to remove insensitive terms from our products and documentation. We are also mindful of the necessity to maintain compatibility with our customers' existing technologies and the need to ensure continuity of service as Oracle's offerings and industry standards evolve. Because of these technical constraints, our effort to remove insensitive terms is ongoing and will take time and external cooperation.

Part I

Getting Started

This part provides an overview of the Oracle Communications Pricing Design Center (PDC) installation and includes the system requirements for installing or upgrading the software. It contains the following chapters:

- [Pricing Design Center Installation Overview](#)
- [Pricing Design Center System Requirements](#)

1

Pricing Design Center Installation Overview

Learn about the procedures for installing and upgrading Oracle Communications Pricing Design Center (PDC).

Topics in this document:

- [Overview of the PDC Installation Procedure](#)
- [Overview of the PDC Upgrade Procedure](#)
- [Ensuring a Successful PDC Installation](#)

Overview of the PDC Installation Procedure

The following is an outline of the installation procedure for the PDC software:

1. Plan your installation. Planning your installation involves:
 - Determining the scale of your implementation (for example, is it a small test system or a large production system?)
 - Assessing how many physical computers you need and which software components to install on which computers
 - Planning the system topology
2. Review system requirements.
3. Perform the following preinstallation tasks:
 - Install and configure Oracle Database
 - Install and configure Oracle WebLogic Server
 - Install and configure Oracle Communications Billing and Revenue Management (BRM)
 - Install Java Runtime Environment (JRE)/Java Development Kit (JDK)
4. Install the complete PDC software.
5. Perform the postinstallation configuration tasks.
6. Verify the installation.

Overview of the PDC Upgrade Procedure

The following is an outline of the procedure for the PDC upgrade:

1. Plan your upgrade.
2. Review system requirements.
3. Perform the following preinstallation tasks:
 - Shut down the current instance.

- Back up your existing PDC installation.
 - Install a compatible version of ECE.
 - Install a compatible version of BRM.
 - Upgrade the PDC database.
4. Install PDC in a different location on the machine on which the existing PDC installation is located.
 5. Perform the postinstallation configuration tasks.
 6. Verify the installation.

Ensuring a Successful PDC Installation

Oracle recommends that the installation and configuration of the Oracle database be performed by an experienced database administrator.

To ensure that the PDC installation is successful, follow these guidelines:

- As you install each component (for example, the Oracle Database and Oracle WebLogic Server), verify that the component installed successfully before continuing the installation process.
- Pay close attention to the system requirements. Before you begin installing the application, ensure that your system has the required base software. In addition, ensure that you know all the required configuration values, such as host names and port numbers.
- Make a note of any new configuration values as you create them. You will be required to enter configuration values later in the procedure.

2

Pricing Design Center System Requirements

Learn about the software and hardware requirements for installing Oracle Communications Pricing Design Center (PDC).

Topics in this document:

- [Software Requirements](#)
- [Hardware Requirements](#)
- [Information Requirements](#)

Software Requirements

PDC is an application that is deployed in an Oracle WebLogic Server domain. You must install and connect all required software for optimal performance. For more information on the supported operating systems, additional software required, and compatible software versions, see "PDC Software Compatibility" in *BRM Compatibility Matrix*.

Hardware Requirements

The number and configuration of the computers that you employ for your PDC installation depend on the scale and the kind of deployment you have planned according to your networks.

[Table 2-1](#) provides the minimal hardware requirement for PDC installed on a single managed server in a WebLogic Server domain.

Table 2-1 PDC Minimum Hardware Requirements

Component	Requirement
Hard disk	1.5 GB of free disk space Note: A minimum of 1.5 GB should be free in the Oracle WebLogic Server domain home.
Processor	Oracle recommends using twin cores, each running at 1.5 GHz CPU.
Memory	A minimum of 4 GB physical memory and 4 GB swap. If you plan to have the database installed on the same server as PDC, the minimum memory requirements increase to 6 GB physical memory and 6 GB swap.

Information Requirements

This section describes the information that you will be required to provide during the PDC installation procedure. You define some of these configuration values when you install and configure Oracle Database and WebLogic Server.

**Note:**

Oracle recommends that you print the tables and record the values for future reference.

Pricing Design Center WebLogic Server Connection Information

Table 2-2 lists the details for the WebLogic Server domain (the domain on which you deploy PDC) that are required during the PDC software installation.

Table 2-2 Pricing Design Center WebLogic Server Connection Information

Field	Description	Value
Host Name	The IP address or the host name of the machine on which the WebLogic Server domain is configured.	-
Port Number	The port number assigned to the WebLogic Server domain administration server.	-
User Name	The WebLogic Server domain administrator user name.	-
Password	The WebLogic Server domain administrator user password.	-
WebLogic Home	The path of the directory in which the WebLogic Server software is installed. For example, <i>Middleware_home/wlserver</i> , where <i>Middleware_home</i> is the directory in which the Oracle Middleware components are installed.	-

PDC Database Connection Information

Table 2-3 lists PDC database details that are required during the PDC software installation.

Table 2-3 PDC Database Connection Information

Field	Description	Value
Host Name	The IP address or the host name of the machine on which the PDC database is configured.	-
Port Number	The port number assigned to the PDC database service.	-
User Name	The PDC database user name. This user should have the following capabilities on the PDC database: create user, grant any role, grant any privileges, select any table for Enterprise edition, and DBA for XE.	-
Password	The database user password.	-
Service Name	The name of the PDC database service.	-

Table 2-3 (Cont.) PDC Database Connection Information

Field	Description	Value
Wallet Location	The directory in which the database wallet is located.	-
Wallet Type	The type of wallet, such as SSO and PKCS12.	-
Wallet Password	The database wallet password.	-

PDC Schema Information

[Table 2-4](#) lists the tablespace details that are required to create the PDC schema during the PDC software installation.

Table 2-4 PDC Schema Information

Field	Description	Value
PDC Tablespace	The name of the tablespace for the PDC schema. This field is case-sensitive.	-
Temp Tablespace	The name of the temporary tablespace for the PDC schema. This field is case-sensitive.	-

BRM Server Information

[Table 2-5](#) lists the BRM server details that are required during the PDC BRM Integration Pack installation.

Table 2-5 BRM Server Information

Field	Description	Value
BRM	The path to the directory in which BRM is installed. The path is defined in the \$PIN_HOME environment variable.	-
BRM Pipeline	The path to the directory in which Pipeline Manager is installed. The path is defined in the \$IFW_HOME environment variable.	-
Perl Home	The path to the directory in which the Perl libraries are installed.	-

BRM Pipeline Manager Database Information

[Table 2-6](#) lists the Pipeline Manager database details that are required during the PDC BRM Integration Pack installation.

Table 2-6 BRM Pipeline Database Information

Field	Description	Value
Host Name	The IP address or the host name of the machine on which the BRM pipeline database is configured.	-
Port Number	The port number assigned to the BRM pipeline database service.	-
User Name	The BRM pipeline database schema user name.	-
Password	The BRM pipeline database schema user password.	-
Service Name	The name of the BRM pipeline database service.	-
Wallet Location	The directory in which the database wallet is located.	-
Wallet Type	Type of the wallet, such as SSO and PKCS12.	-
Wallet Password	The database wallet password.	-

Transformation Cross-Reference Database Information

[Table 2-7](#) lists transformation cross-reference database details that are required during the PDC BRM Integration Pack installation.

Table 2-7 Transformation Cross-Reference Database Information

Field	Description	Value
Hostname	The IP address or the host name of the machine on which the transformation cross-reference database is configured.	-
Port number	The port number assigned to the transformation cross-reference database service.	-
User name	The transformation cross-reference database user name. This user should have the following capabilities on the transformation cross-reference database: create user, grant any role, grant any privileges, select any table for Enterprise edition, and DBA for XE.	-
Password	The transformation cross-reference database user password.	-
Service Name	The name of the transformation cross-reference database service.	-
Wallet Location	The directory in which the database wallet is located.	-
Wallet Type	Type of the wallet, such as SSO and PKCS12.	-
Wallet Password	The database wallet password.	-

Transformation Cross-Reference Schema Information

Table 2-8 lists the tablespace details that are required to create the transformation cross-reference schema during the PDC BRM Integration Pack installation.

Table 2-8 Transformation Cross-Reference Schema Information

Field	Description	Value
PDC Tablespace	The name of the PDC tablespace for the transformation cross-reference schema. This field is case-sensitive.	-
Temp Tablespace	The name of the temporary tablespace for the transformation cross-reference schema. This field is case-sensitive.	-

Migration Cross-Reference Database Information

Table 2-9 lists the migration cross-reference database details that are required during the PDC BRM Integration Pack installation.



Note:

The migration cross-reference database details are required only if you want to migrate pricing and setup components from the BRM database to the PDC database.

Table 2-9 Migration Cross-Reference Database Information

Field	Description	Value
Host Name	The IP address or the host name of the machine on which the migration cross-reference database is configured.	-
Port Number	The port number assigned to the migration cross-reference database service.	-
User Name	The migration cross-reference database user name.	-
Password	The migration cross-reference database user password.	-
Service Name	The name of the migration cross-reference database service.	-
Wallet Location	The directory in which the database wallet is located.	-
Wallet Type	Type of the wallet, such as SSO and PKCS12.	-
Wallet Password	The database wallet password.	-

Migration Cross-Reference Schema Information

Table 2-10 lists the tablespace details that are required to create the migration cross-reference schema during PDC BRM Integration Pack installation.

**Note:**

The migration cross-reference schema details are required only if you want to migrate price lists from the BRM database to the PDC database.

Table 2-10 Migration Cross-Reference Schema Information

Field	Description	Value
PDC Tablespace	The name of the PDC tablespace for the migration cross-reference schema. This field is case-sensitive.	-
Temp Tablespace	The name of the temporary tablespace for the migration cross-reference schema. This field is case-sensitive.	-

Part II

Installing Pricing Design Center

This part describes how to set up and install Oracle Communications Pricing Design Center (PDC). It contains the following chapters:



Note:

Do not use the instructions in this part if you are upgrading from an earlier version of PDC. Use the instructions in this part "[Upgrading Pricing Design Center from 12.x to 15.0](#)" instead.

- [Pricing Design Center Preinstallation Tasks](#)
- [Installing Pricing Design Center](#)
- [Pricing Design Center Postinstallation Tasks](#)

3

Pricing Design Center Preinstallation Tasks

Learn about prerequisite tasks, such as installing and configuring the database, that you perform before installing Oracle Communications Pricing Design Center (PDC).

Topics in this document:

- [Preinstallation Tasks for Installing the PDC Software for the First Time](#)

Preinstallation Tasks for Installing the PDC Software for the First Time

Before installing the complete PDC software, do the following:

1. Install and configure Oracle Database. See "[Installing and Configuring Oracle Database](#)".
2. Install Java Runtime Environment (JRE)/Java Development Kit (JDK). See "[Installing JRE/JDK](#)".
3. Install and configure Oracle WebLogic Server. See "[Installing and Configuring Oracle WebLogic Server](#)".
4. Set the JAVA_HOME environment variable. See "[Setting the JAVA_HOME Environment Variable](#)".
5. Enable JRE permissions. See "[Enabling JRE Permissions](#)".
6. Install the compatible version of BRM on the machine on which you will install PDC BRM Integration Pack. See "Installing BRM" in *BRM Installation Guide*.
See "BRM Suite Compatibility" in *BRM Compatibility Matrix* for the compatible version of BRM.
7. Enable integration between BRM and PDC. See "[Enabling BRM-PDC Integration](#)".

Installing and Configuring Oracle Database

Oracle recommends that the installation and configuration of Oracle Database be performed by an experienced database administrator. To install and configure Oracle Database, see the Oracle Database installation documentation.

When you install the software, do the following:

- Install Oracle Database Enterprise Edition.
- Create the PDC database.
- Create a database to store the transformation cross-reference tables, or use the PDC database to store the transformation cross-reference tables.
- Create a database to store the migration cross-reference tables, or use the PDC database or the transformation cross-reference database to store the migration cross-reference tables.

- (Optional) Create PDC tablespaces and temporary tablespaces for the following:
 - The PDC schema, to store the pricing and setup components.
 - The transformation cross-reference schema, to store tables that map pricing and setup components in PDC to the corresponding component in a target rating engine.
 - The migration cross-reference schema, to store tables that map the pricing and setup components that are migrated from the BRM database to the corresponding component in a target rating engine.

Oracle recommends that you create separate PDC tablespaces and temporary tablespaces for each schema. However, you can use a single PDC tablespace and temporary tablespace to create all the schemas.

Setting the Database Time Zone

The PDC database must have the appropriate local time zone setting.

For more information on setting the time zone, see the *Oracle Database Globalization Support Guide*.



Note:

Ensure that the BRM database and the PDC database are in the same time zone.

After PDC has been installed, the database time zone cannot be changed. Ensure the time zone is correctly set before installing PDC.

Tuning the Database

Table 3-1 and Table 3-2 provide recommended database parameters for tuning your database for the PDC installation. These are the minimum requirements for PDC.

Table 3-1 Database Creation Parameters

Parameter	Recommended Value
SGA+PGA	At least 4 GB in total. Oracle recommends that you use as much memory as you have available in the machine, and also use Automatic Memory Management.
Processes	2000
Connection mode	Dedicated server
Redo log file size	1024 MB minimum

Table 3-2 Database Initialization Parameters

Parameter	Recommended Value
db_file_multiblock_read_count	16
distributed_lock_timeout	7200
dml_locks	9700
job_queue_processes	10
log_buffer	31457280
open_cursors	5000
parallel_max_servers	640
plsql_code_type	NATIVE

Configuring SSL for the PDC Database

You can configure secure sockets layer (SSL) for the Oracle database by creating wallets for storing certificates and then modifying the following configuration files:

- **sqlnet.ora**
- **tnsnames.ora**
- **listener.ora**

You can use the **Orapki** utility to create the wallets.

For information about configuring SSL for the Oracle database, see the Oracle Database documentation.

Installing JRE/JDK

Install the recommended version of JRE/JDK on the machine on which you want to deploy PDC. See "PDC Software Compatibility" in *BRM Compatibility Matrix* for the recommended version of JRE/JDK.

To verify the JRE/JDK version:

1. Go to the command prompt on the machine on which you want to deploy PDC.
2. Enter the following command:

```
java -version
```

The Java version is displayed. For example:

```
java version "1.8.0_221"
```

If the version displayed does not start with **1.8.0_**, JRE/JDK 1.8 is not installed.

For information about installing JRE/JDK, see the Oracle Java documentation.

Installing and Configuring Oracle WebLogic Server

This section describes procedures relating to installing Oracle WebLogic Server and configuring the WebLogic Server domain in which you will deploy PDC.

Downloading and Installing Oracle WebLogic Server

WebLogic Server is a component of the Oracle Fusion Middleware media pack. For the compatible version of WebLogic Server, see "PDC Software Compatibility" in *BRM Compatibility Matrix*.

For information on installing Oracle WebLogic Server and the patches (if any), see the Oracle WebLogic Server documentation on the Oracle Help Center:

<http://docs.oracle.com>

Copying Library JAR Files for PDC Installation

Copy the needed jar files to your PDC implementation.

1. Apply patch **p26626168_122140_Generic.zip** on top of your WebLogic Server installation.
2. If you will be installing the PDC software, copy the following files to a directory on your PDC machine:
 - The **ojdbc8.jar** file from your Oracle database installation
 - *Middleware_home***oracle_common/modules/oracle.pki/oraclepki.jar**
 - *Middleware_home***oracle_common/modules/oracle.osdt/osdt_cert.jar**
 - *Middleware_home***oracle_common/modules/oracle.osdt/osdt_core.jar**

where *Middleware_home* is the ORACLE_HOME directory of your WebLogic Server installation.

3. If you will be installing the BRM Integration Pack, copy the following files to a directory on your PDC machine:
 - The **ojdbc8.jar** file from your Oracle database installation
 - *Middleware_home***oracle_common/modules/oracle.idm/identitystore.jar**
 - *Middleware_home***oracle_common/modules/oracle.jps/jps-api.jar**
 - *Middleware_home***oracle_common/modules/oracle.nlsrtl/orai18n.jar**
 - *Middleware_home***oracle_common/modules/oracle.nlsrtl/orai18n-collation.jar**
 - *Middleware_home***oracle_common/modules/oracle.xdk/xmlparserv2.jar**
 - *Middleware_home***oracle_common/modules/oracle.xdk/xml.jar**
 - *Middleware_home***oracle_common/modules/com.sun.xml.bind.jaxb-impl.jar**
 - *Middleware_home***oracle_common/modules/com.sun.xml.bind.jaxb-core.jar**
 - *Middleware_home***oracle_common/modules/oracle.pki/oraclepki.jar**
 - *Middleware_home***oracle_common/modules/oracle.osdt/osdt_cert.jar**
 - *Middleware_home***oracle_common/modules/oracle.osdt/osdt_core.jar**
 - *Middleware_home***oracle_common/modules/javax.jms.javax.jms-api.jar**

- *Middleware_home/wlserver/modules/javax.transaction.javax.transaction-api.jar*
 - *Middleware_home/wlserver/server/lib/wlthint3client.jar*
 - *Middleware_home/wlserver/server/lib/wlclient.jar*
 - *Middleware_home/wlserver/server/lib/wljmsclient.jar*
 - *Middleware_home/wlserver/server/lib/wljmxclient.jar*
 - *Middleware_home/wlserver/server/lib/wlnmclient.jar*
 - *Middleware_home/wlserver/server/lib/wlsafclient.jar*
4. During the PDC and BRM Integration Pack installation process, the installer will prompt you for the directory in which your prerequisite libraries are located. You will need to enter the path where you copied the JAR files.

 **Note:**

Set the prerequisite library location to the *PDC_Oracle_home/apps/lib* directory.

Applying WebLogic Server Patch

Install Patch 33903365 on top of your WebLogic Server installation.

To apply the WebLogic Server patch:

1. Apply patch **p33903365_122140_Generic.zip** on top of your WebLogic Server 12.2.1.4.0 installation.
2. Restart WebLogic Server.

Installing Oracle Application Development Runtime

Oracle Application Development Runtime must be installed on the machine on which you will install PDC. For more information on the compatible version, see "PDC Software Compatibility" in *BRM Compatibility Matrix*.

Download Oracle Application Development Runtime from the following page:

<https://www.oracle.com/tools/downloads/application-development-framework-downloads.html>

For information on installing Oracle Application Development Runtime, see *Oracle Fusion Middleware Installation Guide* for the appropriate version.

 **Note:**

The Oracle Fusion Middleware Application Developer Installer installs Oracle Application Development Runtime and Oracle Enterprise Manager.

Creating the Oracle WebLogic Server Domain

Before creating a WebLogic Server domain, use the Oracle Fusion Middleware Repository Creation Utility (RCU) to create the required Oracle Identity and Access Management (IAM) database schema. See *Fusion Middleware Repository Creation Utility User's Guide* for more information on RCU.

To create a WebLogic Server domain in which to deploy PDC, see the description of using the Configuration Wizard in the Oracle WebLogic Server documentation. You can use the Configuration Wizard in graphical mode or console mode.

 **Note:**

If you are migrating the PDC pricing data from a source PDC system to a target PDC system that supports ECE, ensure that you create the WebLogic Server domain for the target PDC system on the same machine on which the WebLogic Server domain for the source PDC system exists.

Table 3-3 shows the values to choose when creating the WebLogic Server domain for PDC.

Create the WebLogic Server domain with at least one managed server configured along with the administration server because Oracle recommends that you deploy PDC on a managed server in the production environment.

Table 3-3 Oracle WebLogic Server Domain Configuration Values

Configuration Value	Description
Domain source	Select Generate a domain configured automatically to support the following products. From the list, select Oracle JRF - 12.2.1.2.0 [oracle_common] .
Domain Mode Configuration	Select Production Mode.
JDK Selection	From the Available JDKs list, select the JDK version required for installing PDC. For more information, see <i>BRM Compatibility Matrix</i> .
Optional Configuration	Select the following: <ul style="list-style-type: none"> • Administration Server. Select this option to configure the Oracle WebLogic Server domain administration server. • (Optional) Managed Servers, Clusters and Machines. Select this option if you want to configure only WebLogic Server domain managed servers or machines that host WebLogic servers. Note: PDC does not support WebLogic cluster deployment. • (Optional) Deployments and Services. Select this option if you want to target your deployments to servers.
Administration Server Listen Address	Use a listen address that is equal to a resolvable DNS host or IP address.
Administration Server Listen Port	Enter a free port number.

Table 3-3 (Cont.) Oracle WebLogic Server Domain Configuration Values

Configuration Value	Description
Managed Server Listen Address	(Optional) Enter a listen address that is equal to a resolvable DNS host or IP address.
Managed Server Listen Port	(Optional) Enter a free port number.
Target Deployments to Clusters or Servers	(Optional) Add all libraries to the managed server target and to the administration server.
Target Services to Clusters or Servers	(Optional) Add all services to the managed server target.
SSL Listen Port Enabled	Select the SSL Listen Port Enabled check box.
SSL Listen Port	Enter a free port number.

See *Oracle Fusion Middleware Installation Guide for Oracle Enterprise Content Management Suite* for the appropriate version to see more information on WebLogic Server domains.

You can now start the administration server manually and log in to WebLogic Administration Console.

Configuring SSL for the WebLogic Server Domain

If you want to enable secure communication for PDC, you must configure SSL for the WebLogic Server domain in which you deploy PDC.

To configure SSL for the WebLogic Server domain:

1. Generate the server-side KeyStore file by using the recommended version of the JRE/JDK **keytool** utility. See *Key and Certificate Management Tool* for more information.
2. Export the public certificate from the server-side KeyStore file by using the recommended version of the JRE/JDK **keytool** utility. See *Key and Certificate Management Tool* for more information.
3. Generate the client-side KeyStore file from the exported public certificate by using the recommended version of the JRE/JDK **keytool** utility. See *Key and Certificate Management Tool* for more information.

Note:

Note the path of the client-side KeyStore file. You need to provide this path during the PDC installation if you choose to use SSL.

If you are installing PDC and BRM Integration Pack on different machines, copy the client-side KeyStore file to the machine on which you want to install BRM Integration Pack.

4. Configure SSL for the server on which you want to deploy PDC in WebLogic Server Administration Console. See the Oracle WebLogic Administration Console Help for more information.

5. Enable Java Secure Socket Extension-based SSL for the server on which you want to deploy PDC in WebLogic Server Administration Console. See the Oracle WebLogic Server Administration Console Help for more information.

Configuring the SSL Protocol Version

In a production environment, Oracle recommends the TLSv1 protocol for sending and receiving messages in an SSL connection.

Note:

You need to set the same protocol version for managed servers and the administration server. Ensure that all the managed servers are down when making changes to the administration server for setting up the protocol. Oracle recommends to set the properties in the administration server and then the managed server.

To set the minimum protocol version to TLS version 1.2, specify the following as a command-line option in the WebLogic Server startup parameters:

```
-Dweblogic.security.SSL.minimumProtocolVersion=TLSv1.2
```

Note:

When you set a minimum protocol version, the TLS protocol that is enabled depend on the protocols that are configured in the SSL implementation.

See the discussion about specifying the version of the SSL protocol in the Oracle WebLogic Server documentation for more information. More information is also available in the following support article: "[WebLogic 12.2.1.x Versions That Support TLS 1.3](#)"

Setting the JDBC Path for the WebLogic Server Domain

You must obtain the **ojdbc8.jar** file and set the path to this file for the WebLogic Server domain.

To set the JDBC path for the WebLogic Server domain:

1. Download the **ojdbc8.jar** file and copy it to the *Domain_home\lib* directory, where *Domain_home* is the directory in which the WebLogic Server domain is created.
You can download this file from the following page:
<https://www.oracle.com/database/technologies/appdev/jdbc-downloads.html>
2. Go to the *Middleware_home\user_projects\domains\bin* directory, where *Middleware_home* is the directory in which the Oracle Middleware components are installed.
3. Open the **setDomainEnv.sh** file in a text editor.
4. Add or modify the following entry to point to **ojdbc8.jar**:

```
setDomainEnv.sh CLASSPATH=${Domain_home}/lib/ ojdbc8.jar:${CLASSPATH}
export CLASSPATH
```

5. Save and close the file.

Configuring WebLogic Server to use SSL-Enabled Data Source

You can use the Secure Sockets Layer (SSL)-enabled data source in Oracle WebLogic Server for secured communications.

You must configure WebLogic Server before configuring the data sources. For more information on configuring WebLogic Server, see the discussion about using SSL with data sources and Oracle drivers in the Oracle WebLogic Server documentation and in the following page:

<https://www.oracle.com/middleware/technologies/weblogic/configure-use-jdbcdriverssl.html>

Updating JDBC LLR Table Name

If you are using an existing database schema during installation, the Logging Last Resource (LLR) table name must be changed to avoid errors.

To change the LLR table name:

1. Log in to WebLogic Server Administration Console.
2. In the **Domain Structure** section, expand **Environment** and select **Servers**.
The Summary of Servers page appears.
3. Select the server for which you want to change the LLR table name.
4. Click the **Configuration** tab.
5. Click the **General** subtab.
6. Click **Advanced** to show the advanced configuration options.
7. Set **JDBC LLR Table Name** to a different name.
8. Click **Save**.

For more information on LLR, see the discussion about administrative considerations and limitations for LLR data sources in the WebLogic Server documentation.

Setting the JAVA_HOME Environment Variable

Set the **JAVA_HOME** environment variable to the recommended version of JRE/JDK before running any PDC processes.

Set the **JAVA_HOME** environment variable on the machine on which you want to deploy PDC. For example, in C-shell:

1. Open the **.cshrc** file in a text editor.
2. Add or modify the following entries:

```
setenv JAVA_HOME jre/jdk_path
```

where *jre/jdk_path* is the absolute path to the directory in which JRE/JDK is installed.

For example:

```
setenv JAVA_HOME /pinhome/jre/1.8.0_144
```

3. Save and close the file.
4. Update the environment by running the following command:

```
source .cshrc
```

5. Verify the Java version by running the following command:

```
$JAVA_HOME/bin/java -version
```

The Java version is displayed. For example:

```
java version "1.8.0_144"Java(TM) SE Runtime Environment (build 1.8.0_144-b07)Java HotSpot(TM) 64-Bit Server VM (build 20.60-b01, mixed mode)
```

To set the JAVA_HOME environment variable for the WebLogic Server domain:

1. Go to the *Middleware_home/user_projects/domains/bin* directory, where *Middleware_home* is the directory in which the Oracle Middleware components are installed.
2. Open the **setDomain.sh** file in a text editor.
3. Add or modify the following entries before the **EXTRA_JAVA_PROPERTIES** entry:

```
JAVA_HOME="${JAVA_HOME}"
export JAVA_HOME
```

4. Save and close the file.

Enabling JRE Permissions

To enable JRE permissions:

1. Go to the *jre/jdk_path/lib/security* directory.
2. Open the **java.policy** file in a text editor.
3. Add the following entries to the file:

```
grant (// JMX Java Management eXtensionspermission
javax.management.MBeanTrustPermission "register");;
```

4. Save and close the file.

Enabling BRM-PDC Integration

After installing BRM, enable the BRM-PDC integration in BRM. This enables PDC to transform and transfer pricing components configured in PDC to BRM.

To enable the BRM-PDC integration:

1. Go to *BRM_home/sys/data/config* and run the following command, which creates an editable XML file from the pricing instance of the **/config/business_params** object, where *BRM_home* is the directory in which BRM is installed.

```
BRM_home/bin/pin_bus_params -r BusParamsPricing bus_params_pricing.xml
```

This directory includes the support files used by the **pin_bus_params** utility. To run it from a different directory, see the discussion about the **pin_bus_params** utility in the BRM documentation.

This command creates the XML file named **bus_params_pricing.xml.out** in your working directory. If you do not want this file in your working directory, specify the path as part of the file name.

2. Search the **bus_params_pricing.xml.out** file for the following line:

```
<PriceDesignCenterInst>disabled</PriceDesignCenterInst>
```

3. Change **disabled** to **enabled**.
4. Save the file as **bus_params_pricing.xml**.
5. Run the following command, which loads the updated file into the **/config/business_params** object:

```
BRM_home/bin/pin_bus_params bus_params_pricing.xml
```

6. Read the object with the **testnap** utility or Object Browser to verify that all fields are correct. See "Reading Objects" in *BRM Developer's Guide*.
7. Stop and restart the Connection Manager (CM).

For more information, see "Starting and Stopping the BRM System" in *BRM System Administrator's Guide*.

4

Installing Pricing Design Center

Learn how to install one or more of the following Oracle Communications Pricing Design Center (PDC) components: the PDC software, Oracle Communications Billing and Revenue Management (BRM) Integration Pack, or PDC REST Services Manager.

Topics in this document:

- [About the PDC Installer and PDC Schema](#)
- [About Installing PDC](#)
- [Downloading the PDC Software](#)
- [Installing PDC in GUI Mode](#)
- [Installing PDC in Silent Mode](#)
- [About Installation Logs](#)

About the PDC Installer and PDC Schema

The PDC installer provides the option to install the PDC software, BRM Integration Pack, PDC REST Services Manager, or all three PDC components. For more information about these components, see "PDC System Architecture" in *BRM Concepts*.

The PDC installer also allows you to create a new PDC database schema or reuse your existing PDC database schema. It determines whether to create or reuse the schema by checking the PDC tablespace you provide during the installation process:

- If you point to an empty PDC tablespace, the installer creates a new PDC schema.
- If you point to a PDC tablespace with an existing schema, the installer validates the PDC schema. If the validation succeeds, PDC reuses the existing PDC schema.

Note:

If you choose to reuse an existing PDC schema, you must also choose the same rating engine as the existing PDC installation. That is, if your existing PDC installation uses Elastic Charging Engine (ECE) for usage rating, you cannot switch to the Realtime Rating and Batch Rating Engines. Likewise, if your existing PDC installation uses the Realtime Rating and Batch Rating Engines for usage rating, you cannot switch to ECE. If you attempt to switch rating engines, the PDC installer generates an error and prevents you from proceeding with the installation process.

About Installing PDC

You can install PDC in GUI mode or silent mode. Installing PDC in silent mode lets you perform a non-interactive install of PDC. You can use the silent mode to install PDC quickly.

PDC installation must be performed by a user who has permissions to write to the **oralinventory** directory and the *Middleware_home*/**user_projects/domains** directory, where *Middleware_home* is the directory in which the Oracle Middleware components are installed.

Downloading the PDC Software

You can download and install full versions of the PDC software from the Oracle software delivery website (<https://edelivery.oracle.com>).

Search for and download the **Oracle Communications Pricing Design Center 15.0.0.0.0** software. The package includes the **pdcservice-15.0.0.0.0_generic_full.jar** installer.

Installing PDC in GUI Mode

The steps for installing PDC by using the GUI depend on the PDC components you choose to install:

- To install all PDC components, including the PDC software, BRM Integration Pack, and PDC REST Services Manager, select the **Complete** installation option. See "[Installing All PDC Components](#)".
- To install only the PDC software, select the **Pricing Design Center** installation option. See "[Installing Only the PDC Software](#)".
- To install only BRM Integration Pack, select the **BRM Integration Pack** installation option. See "[Installing Only BRM Integration Pack](#)".
- To install only PDC REST Services Manager, select the **PDC REST Services Manager** option. See "[Installing Only PDC REST Services Manager](#)".

Installing All PDC Components

To install the PDC software, BRM Integration Pack, and PDC REST Services Manager on the same machine:

1. Obtain the PDC software. See "[Downloading the PDC Software](#)".
2. Start the Oracle WebLogic Server domain administration server or the WebLogic Server domain managed server on which you want to deploy PDC, if it is not already started.
3. Ensure that the PDC database is running.

Note:

Ensure that the Oracle Database server is in Running state. The Installer connects to the Oracle Database server to verify the information you entered is valid.

4. Go to the *temp_dir* directory, and run one of the following commands:
 - To start the GUI installer:

```
Java_home/bin/java -jar pdcservice-15.0.0.0.0_generic_full.jar
```

where *Java_home* is the directory in which you installed the latest supported Java version.

- To start the GUI installer and install PDC using the **oralInventory** directory in a different location:

```
Java_home/bin/java -jar pdcserver-15.0.0.0.0_generic_full.jar -invPtrLoc  
FilePath/oraInst.loc
```

where *FilePath* is the path to the directory in which the **oralInst.loc** file is located.

- To start the GUI installer and create a silent installer response file during the installation:

```
Java_home/bin/java -jar pdcserver-15.0.0.0.0_generic_full.jar -record -  
destinationFile path
```

where *path* is the response file location and name.

The Welcome screen appears.

5. Click **Next**.

The Specify Inventory Directory and Credentials screen appears if the **oralInst.loc** file is corrupt or not present. The default location of the **oralInventory** directory is in the **/etc/oralInst.loc** file.

This screen displays the path to the default inventory directory and the default operating system group name.

6. (Optional) To change the default inventory directory details, do the following:

- a. Enter the full path of the inventory directory.
- b. Specify the name of the operating system group that has write permission to the inventory directory.

7. Click **Next**.

The Installation Location screen appears.

8. Enter the full path or browse to the directory in which to install PDC.

9. Click **Next**.

The Installation Type screen appears.

10. Select **Complete** and click **Next**.

The PDC Pre-requisite Libraries Location screen appears.

11. In the **Prerequisite library location** field, enter the full path or browse to the directory in which you copied all of the PDC JAR files. See "[Copying Library JAR Files for PDC Installation](#)" for more information.

12. Click **Next**.

The PDC WebLogic Server screen appears.

13. Enter the following details for the WebLogic Server domain in which you want to deploy PDC:

- a. In the **Host Name** field, enter the IP address or the host name of the machine on which the WebLogic Server domain is configured.
- b. In the **Port Number** field, enter the port number assigned to the WebLogic Server domain administration server.

- c. In the **User Name** field, enter the WebLogic Server domain administrator user name.
- d. In the **Password** field, enter the WebLogic Server domain administrator user password.
- e. In the **WebLogic Home** field, enter the path to the directory in which the WebLogic Server software is installed. For example, *Middleware_home1\wlserver*.
- f. To enable secure communication for PDC, select the **Enable SSL? (Recommended)** check box, and in the **KeyStore Location** field, enter the path of the client-side KeyStore file generated from the exported public certificate using the **keytool** utility.

For more information, see "[Configuring SSL for the WebLogic Server Domain](#)".

- g. To allow the import and export of large XML files into PDC, select **Apply WebLogic tuning parameters**. For information about the WebLogic tuning parameters, see the installer Help.

 **Note:**

If you select this check box, you must restart the WebLogic Server domain after PDC installs successfully.

14. Click **Next**.

The WebLogic Server/Cluster screen appears.

15. Do one of the following:

- To deploy PDC on a WebLogic Server domain administration server, select a WebLogic Server domain administration server from the list.
- To deploy PDC on a WebLogic Server domain managed server, select a WebLogic Server domain managed server from the list.

 **Note:**

Oracle recommends that you deploy PDC on a WebLogic Server managed server. If you select a WebLogic Server managed server, ensure that the WebLogic Server managed server and the node manager are running.

16. Click **Next**.

The PDC Wallet Location and Password screen appears.

17. Enter the following details for the PDC wallet:

- a. In the **Wallet Location** field, enter the path to the directory in which the PDC wallet is located or is to be installed.
- b. In the **Wallet Password** field, enter the PDC wallet password.
- c. In the **Confirm Wallet Password** field, enter the PDC wallet password again.

18. Click **Next**.

The Pricing Design Center Schema User screen appears.

19. Do one of the following:

- If you want to create a PDC schema user during installation, select **Yes** and proceed to step 20.
- If you want to use an existing PDC schema user, select **No** and proceed to step 24.

20. Click **Next**.

The Pricing Design Center System Database Connection screen appears.

21. Enter the following information required to connect to the PDC database:

- a. In the **Host Name** field, enter the IP address or the host name of the machine on which the PDC database is configured.
- b. In the **Port Number** field, enter the port number assigned to the PDC database service.

 **Note:**

If the database is SSL-enabled, enter the SSL port number in the **Port Number** field.

c. In the **User Name** field, enter the PDC database user name.

This user should be the SYSDBA user or should have the following capabilities on the PDC database: grant create user, grant any role, grant any privileges, select any table to *username*, and grant sysdba to *username*.

- d. In the **Password** field, enter the PDC database user password.
- e. In the **Service Name** field, enter the name of the PDC database service.

 **Note:**

Ensure that the Oracle Database server is in Running state. The Installer connects to the Oracle Database server to verify the information you entered is valid.

- f. From the **SSL** list, select the type of SSL connection required for connecting to the PDC database:
 - **No**: SSL authentication is not required.
 - **Yes-One Way**: One-way SSL authentication is required. In this case, the client must authenticate the server's identity.
 - **Yes-Two Way**: Two-way SSL authentication is required. In this case, both the client and server must authenticate each others identity.
- g. If you selected **Yes-One Way** or **Yes-Two Way**, do the following:
 - From the **Wallet Type** list, select the type of wallet to use for secure communication with the database: **SSO** or **PKCS12**.
 - In the **Truststore Wallet Location** field, enter the full path to the directory in which the database wallet is located.

- In the **Truststore Wallet Password** field, enter the TrustStore wallet password to be used for secure communication.
- In the **Keystore Wallet Location** field, enter the full path or browse to the directory in which the database wallet is located.
- In the **Keystore Wallet Password** field, enter the KeyStore wallet password to be used for secure communication.

22. Click **Next**.

The Pricing Design Center Schema screen appears.

23. Enter the following information required to create the PDC schema in the PDC database and proceed to step 26:
- a. In the **User Name** field, enter a PDC schema user name.
 - b. In the **Password** field, enter a PDC schema user password.
 - c. In the **Confirm Password** field, enter the PDC schema user password again.
 - d. In the **PDC Tablespace** field, enter the name of the tablespace for the PDC schema.
 - e. In the **Temp Tablespace** field, enter the name of the temporary tablespace for the PDC schema.

 **Note:**

If you point to a PDC tablespace with an existing schema, the installer validates the PDC schema. If the validation succeeds, PDC re-uses the existing PDC schema. If you point to an empty PDC tablespace, the installer creates a new PDC schema.

24. Click **Next**.

The Pricing Design Center Schema screen appears.

25. Enter the following information required to connect to a PDC database for an existing PDC user:
- a. In the **Host Name** field, enter the IP address or the host name of the machine on which the PDC database is configured.
 - b. In the **Port Number** field, enter the port number assigned to the PDC database service.

 **Note:**

If the database is SSL-enabled, enter the SSL port number in the **Port Number** field.

- c. In the **User Name** field, enter the PDC database user name.

This user should be the SYSDBA user or should have the following capabilities on the PDC database: grant create user, grant any role, grant any privileges, select any table to *username*, and grant sysdba to *username*.

- d. In the **Password** field, enter the PDC database user password.
- e. In the **Service Name** field, enter the name of the PDC database service.

 **Note:**

Ensure that the Oracle Database server is in Running state. The Installer connects to the Oracle Database server to verify the information you entered is valid.

- f. From the **SSL** list, select the type of SSL connection required for connecting to the PDC database:
 - **No**: SSL authentication is not required.
 - **Yes-One Way**: One-way SSL authentication is required. In this case, the client must authenticate the server's identity.
 - **Yes-Two Way**: Two-way SSL authentication is required. In this case, both the client and server must authenticate each others identity.
- g. If you selected **Yes-One Way** or **Yes-Two Way**, do the following:
 - From the **Wallet Type** list, select the type of wallet to use for secure communication with the database: **SSO** or **PKCS12**.
 - In the **Truststore Wallet Location** field, enter the full path to the directory in which the database wallet is located.
 - In the **Truststore Wallet Password** field, enter the TrustStore wallet password to be used for secure communication.
 - In the **Keystore Wallet Location** field, enter the full path or browse to the directory in which the database wallet is located.
 - In the **Keystore Wallet Password** field, enter the KeyStore wallet password to be used for secure communication.

26. Click Next.

The Pricing Design Center System User screen appears.

27. Enter the following information to create a PDC user to access the PDC GUI:

- a. In the **User Name** field, enter a PDC user name.
- b. In the **Password** field, enter a PDC user password.

 **Note:**

- The PDC user password can be a maximum of 12 characters long and should contain at least one non-alphabetic character.
- The user name must not be a part of the password.

- c. In the **Confirm Password** field, enter the PDC user password again.

28. Click Next.

The Select Charging Engine for Usage Rating appears.

29. Do one of the following:

- To use Oracle Communications Billing and Revenue Management (BRM) Elastic Charging Engine (ECE) for usage rating, select **Elastic Charging Engine**.
- To use BRM real-time rating and batch rating engines for usage rating, select **Realtime Rating and Batch Rating Engines**.

 **Note:**

If you choose to reuse an existing PDC schema, you must also choose the same rating engine as the existing PDC installation. That is, if your existing PDC installation uses Elastic Charging Engine (ECE) for usage rating, you cannot switch to the Realtime Rating and Batch Rating Engines. Likewise, if your existing PDC installation uses the Realtime Rating and Batch Rating Engines for usage rating, you cannot switch to ECE. If you attempt to switch rating engines, the PDC installer generates an error and prevents you from proceeding with the installation process.

30. Click **Next**.

The PDC Prerequisite Libraries Location screen appears.

31. In the **Prerequisite library location** field, enter the full path or browse to the directory in which you copied all of the PDC JAR files. See "[Copying Library JAR Files for PDC Installation](#)" for more information.

32. Click **Next**.

The Migration Option screen appears.

33. Do one of the following:

- If you do not want to migrate data, select **Do not install Migration Utility** and proceed to step 38.
- To migrate the BRM real-time and batch rating engines pricing data to a PDC system that supports BRM real-time and batch rating engines, select **Migrate RRE and BRE Pricing Data to PDC** and proceed to step 38.
- To migrate the BRM real-time and batch rating engines pricing data to a PDC system that supports ECE, select **Migrate RRE and BRE Pricing Data to PDC with ECE** and proceed to step 38.
- To migrate the PDC pricing data to a PDC system that supports ECE, select **Migrate PDC Pricing Data to PDC with ECE** and continue with the next step.

34. Click **Next**.

The Source WebLogic Administration Server Connection screen appears.

35. If you are migrating the PDC pricing data to a PDC system that supports ECE, enter the following details for the WebLogic Server domain in which you deployed the source PDC system:

- a. In the **Host Name** field, enter the IP address or the host name of the machine on which the WebLogic Server domain for the source PDC system is configured.

- b. In the **Port Number** field, enter the port number assigned to the WebLogic Server domain administration server.

 **Note:**

If you selected a WebLogic Server domain managed server in step 15, enter the port number to the managed server.

- c. In the **User Name** field, enter the WebLogic Server domain administrator user name.
- d. In the **Password** field, enter the WebLogic Server domain administrator user password.
- e. In the **WebLogic Home** field, enter the path of the directory where the Oracle WebLogic Server software is installed.
- f. Do one of the following:
 - If you do not want to enable secure communication for PDC, deselect the **Enable SSL?** check box.
 - To enable secure communication for PDC, leave the **Enable SSL?** check box selected, and in the **KeyStore Location** field, enter the path of the client-side KeyStore file generated from the exported public certificate using the **keytool** utility.

For more information, see "[Configuring SSL for the WebLogic Server Domain](#)".

36. Click Next.

The Target Pricing Design Center WebLogic Server Connection screen appears.

37. If you are migrating the PDC pricing data to a PDC system that supports ECE, enter the following details for the WebLogic Server domain in which you deployed the target PDC system:

- a. In the **Host Name** field, enter the IP address or the host name of the machine on which the WebLogic Server domain for the target PDC system is configured.
- b. In the **Port Number** field, enter the port number assigned to the WebLogic Server domain administration server.
- c. In the **User Name** field, enter the WebLogic Server domain administrator user name.
- d. In the **Password** field, enter the WebLogic Server domain administrator user password.
- e. Do one of the following:
 - If you do not want to enable secure communication for PDC, deselect the **Enable SSL?** check box.
 - To enable secure communication for PDC, leave the **Enable SSL?** check box selected, and in the **KeyStore Location** field, enter the path of the client-side KeyStore file generated from the exported public certificate using the **keytool** utility.

For more information, see "[Configuring SSL for the WebLogic Server Domain](#)".

38. Click Next.

The Pricing Design Center WebLogic Server Connection screen appears.

39. Enter the following details for the WebLogic Server domain in which you deployed PDC:
 - a. In the **Host Name** field, enter the IP address or the host name of the machine on which the WebLogic Server domain is configured.
 - b. In the **Port Number** field, enter the port number assigned to the WebLogic Server domain administration server.
 - c. In the **User Name** field, enter the WebLogic Server domain administrator user name.
 - d. In the **Password** field, enter the WebLogic Server domain administrator user password.
 - e. Do one of the following:

If you do not want to enable secure communication for PDC, deselect the **Enable SSL?** check box.

To enable secure communication for PDC, leave the **Enable SSL?** check box selected, and in the **KeyStore Location** field, enter the path of the client-side KeyStore file generated from the exported public certificate using the **keytool** utility.

For more information, see "[Configuring SSL for the WebLogic Server Domain](#)".
40. Click **Next**.

The BRM Integration Pack Wallet Location and Password screen appears.
41. Enter the following details for the BRM Integration Pack wallet:
 - a. In the **Wallet Location** field, enter the path to the directory in which the BRM Integration Pack wallet is located or is to be installed.
 - b. In the **Wallet Password** field, enter the BRM Integration Pack wallet password.
 - c. In the **Confirm Wallet Password** field, enter the BRM Integration Pack wallet password again.
42. Click **Next**.

The BRM Server Location screen appears.
43. Enter the BRM batch and real-time rating engine details:
 - a. In the **BRM** field, enter the full path or browse to the directory in which BRM is installed.
 - b. In the **BRM Pipeline** field, enter the full path or browse to the directory in which Pipeline Manager is installed.
 - c. In the **Perl Home** field, enter the full path or browse to the directory in which the Perl libraries for BRM are installed.
44. Click **Next**.

The BRM Database Connection screen appears.
45. Enter the following information required to connect to the BRM database:
 - a. In the **Host Name** field, enter the IP address or the host name of the machine on which the BRM database is configured.
 - b. In the **Port Number** field, enter the port number assigned to the BRM database service.

 **Note:**

If the database is SSL-enabled, enter the SSL port number in the **Port Number** field.

- c. In the **User Name** field, enter the BRM database user name.

This user should be the SYSDBA user or should have the following capabilities on the BRM database: grant create user, grant any role, grant any privileges, select any table to *username*, and grant sysdba to *username*.

- d. In the **Password** field, enter the BRM database user password.
- e. In the **Service Name** field, enter the name of the BRM database service.

 **Note:**

Ensure that the Oracle Database server is in Running state. The Installer connects to the Oracle Database server to verify the information you entered is valid.

- f. From the **SSL** list, select the type of SSL connection required for connecting to the BRM database:

- **No:** SSL authentication is not required.
- **Yes-One Way:** One-way SSL authentication is required. In this case, the client must authenticate the server's identity.
- **Yes-Two Way:** Two-way SSL authentication is required. In this case, both the client and server must authenticate each others identity.

- g. If you selected **Yes-One Way** or **Yes-Two Way**, do the following:

- From the **Store Type** list, select the type of wallet to use for secure communication with the database: **SSO** or **PKCS12**.
- In the **Truststore Wallet Location** field, enter the full path to the directory in which the database wallet is located.
- In the **Truststore Wallet Password** field, enter the TrustStore wallet password to be used for secure communication.
- In the **Keystore Wallet Location** field, enter the full path or browse to the directory in which the database wallet is located.
- In the **Keystore Wallet Password** field, enter the KeyStore wallet password to be used for secure communication.

46. Click **Next**.

The PDC Cross-Reference Schema User screen appears.

47. Do one of the following:

- If you want to create a transformation cross-reference schema user during installation, select **Yes** and proceed to step 48.
- If you want to use an existing transformation cross-reference schema user, select **No** and proceed to step 52.

48. Click Next.

The Transformation Cross-Reference Database Connection screen appears.

49. Enter the following information required to connect to the transformation cross-reference database:

- a. In the **Host Name** field, enter the IP address or the host name of the machine on which to create the transformation cross-reference schema.
- b. In the **Port Number** field, enter the port number assigned to the transformation cross-reference database service.

 **Note:**

If the database is SSL-enabled, enter the SSL port number in the **Port Number** field.

- c. In the **User Name** field, enter the transformation cross-reference database user name.

This user should be the SYSDBA user or should have the following capabilities on the transformation cross-reference database: grant create user, grant any role, grant any privileges, select any table to *username*, and grant sysdba to *username*.

- d. In the **Password** field, enter the transformation cross-reference database user password.
- e. In the **Service Name** field, enter the name of the transformation cross-reference database service.

 **Note:**

Ensure that the Oracle Database server is in Running state. The Installer connects to the Oracle Database server to verify the information you entered is valid.

- f. From the **SSL** list, select the type of SSL connection required for connecting to the transformation cross-reference database:
 - **No**: SSL authentication is not required.
 - **Yes-One Way**: One-way SSL authentication is required. In this case, the client must authenticate the server's identity.
 - **Yes-Two Way**: Two-way SSL authentication is required. In this case, both the client and server must authenticate each others identity.
- g. If you selected **Yes-One Way** or **Yes-Two Way**, do the following:
 - From the **Store Type** list, select the type of wallet to use for secure communication with the database: **SSO** or **PKCS12**.
 - In the **Truststore Wallet Location** field, enter the full path to the directory in which the database wallet is located.

- In the **Truststore Wallet Password** field, enter the TrustStore wallet password to be used for secure communication.
- In the **Keystore Wallet Location** field, enter the full path or browse to the directory in which the database wallet is located.
- In the **Keystore Wallet Password** field, enter the KeyStore wallet password to be used for secure communication.

50. Click **Next**.

The Transformation Cross-Reference Schema screen appears.

51. Enter the following information required to create the transformation cross-reference schema in the transformation cross-reference database and proceed to step 54:

 **Note:**

If you are migrating the pricing data from a source PDC system to a target PDC system that supports ECE, provide the details of the transformation cross-reference schema that you created for the source PDC system.

- a. In the **User Name** field, enter a transformation cross-reference schema user name.
- b. In the **Password** field, enter a transformation cross-reference schema user password.
- c. In the **Confirm Password** field, enter the transformation cross-reference schema user password again.
- d. In the **PDC Tablespace** field, enter the name of the tablespace for the transformation cross-reference schema.
- e. In the **Temp Tablespace** field, enter the name of the temporary tablespace for the transformation cross-reference schema.

52. Click **Next**.

The Transformation Cross-Reference Schema screen appears.

53. Enter the following information required to connect to the transformation cross-reference database:

 **Note:**

If you are migrating the pricing data from a source PDC system to a target PDC system that supports ECE, provide the details of the transformation cross-reference schema that you created for the source PDC system.

- a. In the **Host Name** field, enter the IP address or the host name of the machine on which the transformation cross-reference database is configured.
- b. In the **Port Number** field, enter the port number assigned to the transformation cross-reference database service.

 **Note:**

If the database is SSL-enabled, enter the SSL port number in the **Port Number** field.

- c. In the **Service Name** field, enter the name of the transformation cross-reference database service.
 - d. In the **User Name** field, enter the transformation cross-reference schema user name.
 - e. In the **Password** field, enter the transformation cross-reference schema user password.
 - f. Do one of the following:
 - If you do not want to enable secure communication for the transformation cross-reference database, leave the **SSL Enabled** check box deselected. This is deselected by default.
 - To enable secure communication for the transformation cross-reference database, select the **SSL Enabled** check box.
 - g. If you selected **SSL Enabled**, do the following:
 - In the **Wallet Location** field, enter the full path or browse to the directory in which the database wallet is located. For example, *wallet_home/cwallet.sso* or *wallet_home/ewallet.p12*.
 - From the **Wallet Type** list, select the wallet type.
 - In the **Wallet Password** field, enter the database wallet password if the wallet type is **PKCS12**.
54. Click **Next**.
- The PDC User screen appears.
55. Enter the PDC user information.
- a. In the **User Name** field, enter the PDC user name.
 - b. In the **Password** field, enter the PDC user password.
56. Do one of the following:
- Click **Next**.
 - The Migration Cross-Reference Database Connection screen appears.
 - If you selected **Do not install Migration utility** in step 13, proceed to step 66.
57. Enter the following information required to connect to the migration cross-reference database:
- a. In the **Host Name** field, enter the IP address or the host name of the machine on which to create the migration cross-reference database.
 - b. In the **Port Number** field, enter the port number assigned to the migration cross-reference database service.

 **Note:**

If the database is SSL-enabled, enter the SSL port number in the **Port Number** field.

- c. In the **User Name** field, enter the migration cross-reference database user name.
This user should be the SYSDBA user or should have the following capabilities on the migration cross-reference database: grant create user, grant any role, grant any privileges, select any table to *username*, and grant sysdba to *username*.
- d. In the **Password** field, enter the migration cross-reference database user password.
- e. In the **Service Name** field, enter the name of the migration cross-reference database service.

 **Note:**

Ensure that the Oracle Database server is in Running state. The Installer connects to the Oracle Database server to verify the information you entered is valid.

- f. From the **SSL** list, select the type of SSL connection required for connecting to the migration cross-reference database:
 - **No**: SSL authentication is not required.
 - **Yes-One Way**: One-way SSL authentication is required. In this case, the client must authenticate the server's identity.
 - **Yes-Two Way**: Two-way SSL authentication is required. In this case, both the client and server must authenticate each others identity.
- g. If you selected **Yes-One Way** or **Yes-Two Way**, do the following:
 - From the **Wallet Type** list, select the type of wallet to use for secure communication with the database: **SSO** or **PKCS12**.
 - In the **Truststore Wallet Location** field, enter the full path to the directory in which the database wallet is located.
 - In the **Truststore Wallet Password** field, enter the TrustStore wallet password to be used for secure communication.
 - In the **Keystore Wallet Location** field, enter the full path or browse to the directory in which the database wallet is located.
 - In the **Keystore Wallet Password** field, enter the KeyStore wallet password to be used for secure communication.

58. Click Next.

The Migration Cross-Reference Schema screen appears.

59. Enter the following information required to create the migration cross-reference schema in the migration cross-reference database:

- a. In the **User Name** field, enter a migration cross-reference schema user name.
- b. In the **Password** field, enter a migration cross-reference schema user password.

- c. In the **PDC Tablespace** field, enter the name of the PDC tablespace for the migration cross-reference schema.
 - d. In the **Temp Tablespace** field, enter the name of the temporary tablespace for the migration cross-reference schema.
60. Do one of the following:
 - Click **Next**.
The Migration User screen appears.
 - If you are migrating the PDC pricing data to a PDC system that supports ECE, proceed to step 62.
61. Enter the migration user details and proceed to step 66.
 - a. In the **User Name** field, enter a migration user name.
 - b. In the **Password** field, enter a migration user password.
 - c. In the **Confirm Password** field, enter the migration user password again.
62. Click **Next**.
The Source Migration User screen appears.
63. If you are migrating the PDC pricing data to a PDC system that supports ECE, enter the migration user details that you use to run the migration utility in the source PDC system:
 - a. In the **User Name** field, enter the migration user name.
 - b. In the **Password** field, enter the migration user password.
 - c. In the **Confirm Password** field, enter the migration user password again.
64. Click **Next**.
The Target Migration User screen appears.
65. If you are migrating the PDC pricing data to a PDC system that supports ECE, enter the migration user details that you want to use to run the migration utility in the target PDC system:
 - a. In the **User Name** field, enter the migration user name.
 - b. In the **Password** field, enter the migration user password.
66. Click **Next**.
The Installation Summary screen appears.
67. Review the selections you have made in the preceding screens, and click **Install**.
The Installation Progress screen appears.

 **Note:**

After the installation begins, clicking **Stop installation** stops the installation process, but the files that are already copied are not removed.

68. When the installation is done, click **Next**. The Installation Complete screen appears.

Note down the provided URL, because you will need it to access PDC.

69. Click **Finish** to complete and exit.
70. If you selected **Apply WebLogic tuning parameters**, you must restart the WebLogic Server domain.

See "[Verifying the Pricing Design Center Installation](#)" for information on verifying the successful installation of PDC.

See "[About Installation Logs](#)" for information on PDC Installer logs.

Installing Only the PDC Software

To install only the PDC software:

1. Obtain the PDC software. See "[Downloading the PDC Software](#)".
2. Start the Oracle WebLogic Server domain administration server or the WebLogic Server domain managed server on which you want to deploy PDC, if it is not already started.
3. Ensure that the PDC database is running.

Note:

Ensure that the Oracle Database server is in Running state. The Installer connects to the Oracle Database server to verify the information you entered is valid.

4. Go to the *temp_dir* directory, and run one of the following commands:

- To start the GUI installer:

```
Java_home/bin/java -jar pdcserver-15.0.0.0.0_generic_full.jar
```

where *Java_home* is the directory in which you installed the latest supported Java version.

- To start the GUI installer and install PDC using the **oralInventory** directory in a different location:

```
Java_home/bin/java -jar pdcserver-15.0.0.0.0_generic_full.jar -invPtrLoc  
FilePath/oraInst.loc
```

where *FilePath* is the path to the directory in which the **oralInst.loc** file is located.

- To start the GUI installer and create a silent installer response file during the installation:

```
Java_home/bin/java -jar pdcserver-15.0.0.0.0_generic_full.jar -record -  
destinationFile path
```

where *path* is the response file location and name.

The Welcome screen appears.

5. Click **Next**.

The Specify Inventory Directory and Credentials screen appears if the **oralInst.loc** file is corrupt or not present. The default location of the **oralInventory** directory is in the **/etc/oralInst.loc** file.

This screen displays the path to the default inventory directory and the default operating system group name.

6. (Optional) To change the default inventory directory details, do the following:
 - a. Enter the full path of the inventory directory.
 - b. Specify the name of the operating system group that has write permission to the inventory directory.

7. Click **Next**.

The Installation Location screen appears.

8. Enter the full path or browse to the directory in which to install PDC.

9. Click **Next**.

The Installation Type screen appears.

10. Select **Pricing Design Center** and click **Next**.

The PDC WebLogic Server screen appears.

11. Enter the following details for the WebLogic Server domain in which you want to deploy PDC:
 - a. In the **Host Name** field, enter the IP address or the host name of the machine on which the WebLogic Server domain is configured.
 - b. In the **Port Number** field, enter the port number assigned to the WebLogic Server domain administration server.
 - c. In the **User Name** field, enter the WebLogic Server domain administrator user name.
 - d. In the **Password** field, enter the WebLogic Server domain administrator user password.
 - e. In the **WebLogic Home** field, enter the path to the directory in which the WebLogic Server software is installed. For example, *Middleware_home1\wlserver*.
 - f. To enable secure communication for PDC, select the **Enable SSL? (Recommended)** check box, and in the **KeyStore Location** field, enter the path of the client-side KeyStore file generated from the exported public certificate using the **keytool** utility.

For more information, see "[Configuring SSL for the WebLogic Server Domain](#)".

- g. To allow the import and export of large XML files into PDC, select **Apply WebLogic tuning parameters**. For information about the WebLogic tuning parameters, see the installer Help.

 **Note:**

If you select this check box, you must restart the WebLogic Server domain after PDC installs successfully.

12. Click **Next**.

The PDC Wallet Location and Password screen appears.

13. Enter the following details for the PDC wallet:

- a. In the **Wallet Location** field, enter the path to the directory in which the PDC wallet is located or is to be installed.
 - b. In the **Wallet Password** field, enter the PDC wallet password.
 - c. In the **Confirm Wallet Password** field, enter the PDC wallet password again.
14. Click **Next**.

The WebLogic Server screen appears.

15. Do one of the following:
- To deploy PDC on a WebLogic Server domain administration server, select a WebLogic Server domain administration server from the list.
 - To deploy PDC on a WebLogic Server domain managed server, select a WebLogic Server domain managed server from the list.

 **Note:**

Oracle recommends that you deploy PDC on a WebLogic Server managed server. If you select a WebLogic Server managed server, ensure that the WebLogic Server managed server and the node manager are running.

16. Click **Next**.

The Pricing Design Center Schema User screen appears.

17. Do one of the following:
- If you want to create a PDC schema user during installation, select **Yes** and proceed to step 18.
 - If you want to use an existing PDC schema user, select **No** and proceed to step 22.

18. Click **Next**.

The Pricing Design Center System Database Connection screen appears.

19. Enter the following information required to connect to the PDC database:
- a. In the **Host Name** field, enter the IP address or the host name of the machine on which to create the PDC database schema.
 - b. In the **Port Number** field, enter the port number assigned to the PDC database service.

 **Note:**

If the database is SSL-enabled, enter the SSL port number in the **Port Number** field.

- c. In the **User Name** field, enter the PDC database user name.

This user should be the SYSDBA user or should have the following capabilities on the PDC database: grant create user, grant any role, grant any privileges, select any table to *username*, and grant sysdba to *username*.

- d. In the **Password** field, enter the PDC database user password.

- e. In the **Service Name** field, enter the name of the PDC database service.

 **Note:**

Ensure that the Oracle Database server is in Running state. The Installer connects to the Oracle Database server to verify the information you entered is valid.

- f. From the **SSL** list, select the type of SSL connection required for connecting to the PDC database:
- **No:** SSL authentication is not required.
 - **Yes-One Way:** One-way SSL authentication is required. In this case, the client must authenticate the server's identity.
 - **Yes-Two Way:** Two-way SSL authentication is required. In this case, both the client and server must authenticate each others identity.
- g. If you selected **Yes-One Way** or **Yes-Two Way**, do the following:
- From the **Wallet Type** list, select the type of wallet to use for secure communication with the database: **SSO** or **PKCS12**.
 - In the **Truststore Wallet Location** field, enter the full path to the directory in which the database wallet is located.
 - In the **Truststore Wallet Password** field, enter the TrustStore wallet password to be used for secure communication.
 - In the **Keystore Wallet Location** field, enter the full path or browse to the directory in which the database wallet is located.
 - In the **Keystore Wallet Password** field, enter the KeyStore wallet password to be used for secure communication.

20. Click **Next**.

The Pricing Design Center Schema screen appears.

21. Enter the following information required to create the PDC schema in the PDC database and proceed to step 24:
- a. In the **User Name** field, enter a PDC schema user name.
 - b. In the **Password** field, enter a PDC schema user password.
 - c. In the **Confirm Password** field, enter the PDC schema user password again.
 - d. In the **PDC Tablespace** field, enter the name of the tablespace for the PDC schema.
 - e. In the **Temp Tablespace** field, enter the name of the temporary tablespace for the PDC schema.

 **Note:**

If you point to a PDC tablespace with an existing schema, the installer validates the PDC schema. If the validation succeeds, PDC re-uses the existing PDC schema. If you point to an empty PDC tablespace, the installer creates a new PDC schema.

22. Click Next.

The Pricing Design Center Schema screen appears.

23. Enter the following information required to connect to an existing PDC schema:

- a. In the **Host Name** field, enter the IP address or the host name of the machine with the PDC database schema.
- b. In the **Port Number** field, enter the port number assigned to the PDC database service.

 **Note:**

If the database is SSL-enabled, enter the SSL port number in the **Port Number** field.

- c. In the **User Name** field, enter the PDC database user name.

This user should be the SYSDBA user or should have the following capabilities on the PDC database: grant create user, grant any role, grant any privileges, select any table to *username*, and grant sysdba to *username*.

- d. In the **Password** field, enter the PDC database user password.
- e. In the **Service Name** field, enter the name of the PDC database service.

 **Note:**

Ensure that the Oracle Database server is in Running state. The Installer connects to the Oracle Database server to verify the information you entered is valid.

- f. From the **SSL** list, select the type of SSL connection required for connecting to the PDC database:
 - **No**: SSL authentication is not required.
 - **Yes-One Way**: One-way SSL authentication is required. In this case, the client must authenticate the server's identity.
 - **Yes-Two Way**: Two-way SSL authentication is required. In this case, both the client and server must authenticate each others identity.
- g. If you selected **Yes-One Way** or **Yes-Two Way**, do the following:
 - From the **Wallet Type** list, select the type of wallet to use for secure communication with the database: **SSO** or **PKCS12**.

- In the **Truststore Wallet Location** field, enter the full path to the directory in which the database wallet is located.
- In the **Truststore Wallet Password** field, enter the TrustStore wallet password to be used for secure communication.
- In the **Keystore Wallet Location** field, enter the full path or browse to the directory in which the database wallet is located.
- In the **Keystore Wallet Password** field, enter the KeyStore wallet password to be used for secure communication.

24. Click **Next**.

The Pricing Design Center System Database Connection screen appears.

25. Enter the following information required to connect to the PDC database:

- a. In the **Host Name** field, enter the IP address or the host name of the machine on which to create the PDC database schema.
- b. In the **Port Number** field, enter the port number assigned to the PDC database service.

 **Note:**

If the database is SSL-enabled, enter the SSL port number in the **Port Number** field.

- c. In the **User Name** field, enter the PDC database user name.
This user should be the SYSDBA user or should have the following capabilities on the PDC database: grant create user, grant any role, grant any privileges, select any table to *username*, and grant sysdba to *username*.
- d. In the **Password** field, enter the PDC database user password.
- e. In the **Service Name** field, enter the name of the PDC database service.

 **Note:**

Ensure that the Oracle Database server is in Running state. The Installer connects to the Oracle Database server to verify the information you entered is valid.

- f. From the **SSL** list, select the type of SSL connection required for connecting to the PDC database:
 - **No**: SSL authentication is not required.
 - **Yes-One Way**: One-way SSL authentication is required. In this case, the client must authenticate the server's identity.
 - **Yes-Two Way**: Two-way SSL authentication is required. In this case, both the client and server must authenticate each others identity.
- g. If you selected **Yes-One Way** or **Yes-Two Way**, do the following:

- From the **Wallet Type** list, select the type of wallet to use for secure communication with the database: **SSO** or **PKCS12**.
- In the **Truststore Wallet Location** field, enter the full path to the directory in which the database wallet is located.
- In the **Truststore Wallet Password** field, enter the TrustStore wallet password to be used for secure communication.
- In the **Keystore Wallet Location** field, enter the full path or browse to the directory in which the database wallet is located.
- In the **Keystore Wallet Password** field, enter the KeyStore wallet password to be used for secure communication.

26. Click **Next**.

The Pricing Design Center Schema screen appears.

27. Enter the following information required to create the PDC schema in the PDC database:

- a. In the **User Name** field, enter a PDC schema user name.
- b. In the **Password** field, enter a PDC schema user password.
- c. In the **PDC Tablespace** field, enter the name of the tablespace for the PDC schema.
- d. In the **Temp Tablespace** field, enter the name of the temporary tablespace for the PDC schema.

28. Click **Next**.

The Pricing Design Center System User screen appears.

29. Enter the following information to create a PDC user to access the PDC GUI:

- a. In the **User Name** field, enter a PDC user name.
- b. In the **Password** field, enter a PDC user password.

 **Note:**

- The PDC user password can be a maximum of 12 characters long and should contain at least one non-alphabetic character.
- The user name must not be a part of the password.

- c. In the **Confirm Password** field, enter the PDC user password again.

30. Click **Next**.

The Select Charging Engine for Usage Rating appears.

31. Do one of the following:

- To use Oracle Communications Billing and Revenue Management (BRM) Elastic Charging Engine (ECE) for usage rating, select **Elastic Charging Engine**.
- To use BRM real-time rating and batch rating engines for usage rating, select **Realtime Rating and Batch Rating Engines**.

 **Note:**

If you choose to reuse an existing PDC schema, you must also choose the same rating engine as the existing PDC installation. That is, if your existing PDC installation uses Elastic Charging Engine (ECE) for usage rating, you cannot switch to the Realtime Rating and Batch Rating Engines. Likewise, if your existing PDC installation uses the Realtime Rating and Batch Rating Engines for usage rating, you cannot switch to ECE. If you attempt to switch rating engines, the PDC installer generates an error and prevents you from proceeding with the installation process.

32. Click **Next.**

The Installation Summary screen appears.

33. Review the selections you have made in the preceding screens, and click **Install.**

The Installation Progress screen appears.

 **Note:**

After the installation begins, clicking **Stop installation** stops the installation process, but the files that are already copied are not removed.

34. When the installation is done, click **Next.** The Installation Complete screen appears.

Note down the provided URL, because you will need it to access PDC.

35. Click **Finish to complete and exit.**

36. If you selected **Apply WebLogic tuning parameters, you must restart the WebLogic Server domain.**

See "[Verifying the Pricing Design Center Installation](#)" for information on verifying the successful installation of PDC.

See "[About Installation Logs](#)" for information on PDC Installer logs.

Installing Only BRM Integration Pack

BRM Integration Pack is a set of utilities that transform and transfer pricing components configured in PDC to the BRM system. If BRM and Pipeline Manager are installed on different machines, you must also install Pipeline Configuration Manager. For instructions on how to install Pipeline Configuration Manager, see *BRM Installation Guide*.

 **Note:**

BRM Integration Pack installation must be performed as the Linux user who installed BRM; for example, **pin_user**.

To install only BRM Integration Pack:

1. Obtain the PDC software. See "[Downloading the PDC Software](#)".
2. Start the Oracle WebLogic Server domain administration server or the managed server on which you want to deploy PDC, if it is not already started.
3. Verify that you are able to connect to the BRM database.
4. Go to the *temp_dir* directory, and run one of the following commands:

- To start the GUI installer:

```
Java_home/bin/java -jar pdcserver-15.0.0.0.0_generic_full.jar
```

where *Java_home* is the directory in which you installed the latest supported Java version.

- To start the GUI installer and install PDC using the **oralInventory** directory in a different location:

```
Java_home/bin/java -jar pdcserver-15.0.0.0.0_generic_full.jar -invPtrLoc  
FilePath/oraInst.loc
```

where *FilePath* is the path to the directory in which the **oralInst.loc** file is located.

- To start the GUI installer and create a silent installer response file during the installation:

```
Java_home/bin/java -jar pdcserver-15.0.0.0.0_generic_full.jar -record -  
destinationFile path
```

where *path* is the response file location and name.

The Welcome screen appears.

5. Click **Next**.

The Specify Inventory Directory and Credentials screen appears if the **oralInst.loc** file is corrupt or not present. The default location of the **oralInventory** directory is in the **etc/oralInst.loc** file.

This screen displays the path to the default inventory directory and the default operating system group name.

6. (Optional) To change the default inventory directory details, do the following:
 - a. Enter the full path of the inventory directory.
 - b. Specify the name of the operating system group that has write permission to the inventory directory.

7. Click **Next**.

The Installation Location screen appears.

8. Enter the full path or browse to the directory in which to install BRM Integration Pack.

 **Note:**

If you are installing BRM Integration Pack on the machine on which PDC is installed, then you must provide a different name and path for the BRM Integration Pack installation.

9. Click **Next**.
The Installation Type screen appears.
10. Select **BRM Integration Pack** and click **Next**.
The BRM Integration Pack Pre-requisite Libraries Location screen appears.
11. In the **Prerequisite library location** field, enter the full path or browse to the directory in which you copied all of the PDC JAR files. See "[Copying Library JAR Files for PDC Installation](#)" for more information.
12. Click **Next**.
The Migration Option screen appears.
13. Do one of the following:
 - If you do not want to migrate data, select **Do not install Migration Utility** and proceed to step 18.
 - To migrate the BRM real-time and batch rating engines pricing data to a PDC system that supports BRM real-time and batch rating engines, select **Migrate RRE and BRE Pricing Data to PDC** and proceed to step 18.
 - To migrate the BRM real-time and batch rating engines pricing data to a PDC system that supports ECE, select **Migrate RRE and BRE Pricing Data to PDC with ECE** and proceed to step 18.
 - To migrate the PDC pricing data to a PDC system that supports ECE, select **Migrate PDC Pricing Data to PDC with ECE** and proceed to step 14.
14. Click **Next**.
The Source WebLogic Administration Server Connection screen appears.
15. If you are migrating the PDC pricing data to a PDC system that supports ECE, enter the following details for the WebLogic Server domain in which you deployed the source PDC system:
 - a. In the **Host Name** field, enter the IP address or the host name of the machine on which the WebLogic Server domain for the source PDC system is configured.
 - b. In the **Port Number** field, enter the port number assigned to the WebLogic Server domain administration server.

 **Note:**

If you selected a WebLogic Server domain managed server during the PDC installation, enter the port number to the managed server.

- c. In the **User Name** field, enter the WebLogic Server domain administrator user name.
- d. In the **Password** field, enter the WebLogic Server domain administrator user password.
- e. In the **WebLogic Home** field, enter the path of the directory where the Oracle WebLogic Server software is installed.
- f. Do one of the following:

- If you do not want to enable secure communication for PDC, deselect the **Enable SSL?** check box.
- To enable secure communication for PDC, leave **Enable SSL?** check box selected, and in the **KeyStore Location** field, enter the path of the client-side KeyStore file generated from the exported public certificate using the **keytool** utility.

For more information, see "[Configuring SSL for the WebLogic Server Domain](#)".

16. Click Next.

The Target Pricing Design Center WebLogic Server Connection screen appears.

17. If you are migrating the PDC pricing data to a PDC system that supports ECE, enter the following details for the WebLogic Server domain in which you deployed the target PDC system:

- a.** In the **Host Name** field, enter the IP address or the host name of the machine on which the WebLogic Server domain for the target PDC system is configured.
- b.** In the **Port Number** field, enter the port number assigned to the WebLogic Server domain administration server.
- c.** In the **User Name** field, enter the WebLogic Server domain administrator user name.
- d.** In the **Password** field, enter the WebLogic Server domain administrator user password.
- e.** Do one of the following:
 - If you do not want to enable secure communication for PDC, deselect the **Use SSL?** check box.
 - To enable secure communication for PDC, leave the **Use SSL?** check box selected, and in the **KeyStore Location** field, enter the path of the client-side KeyStore file generated from the exported public certificate using the **keytool** utility.

For more information, see "[Configuring SSL for the WebLogic Server Domain](#)".

18. Click Next.

The Pricing Design Center WebLogic Server Connection screen appears.

19. Enter the following details for the WebLogic Server domain in which you deployed PDC:

- a.** In the **Host Name** field, enter the IP address or the host name of the machine on which the WebLogic Server domain is configured.
- b.** In the **Port Number** field, enter the port number assigned to the WebLogic Server domain administration server.
- c.** In the **User Name** field, enter the WebLogic Server domain administrator user name.
- d.** In the **Password** field, enter the WebLogic Server domain administrator user password.
- e.** Do one of the following:
 - If you do not want to enable secure communication for PDC, deselect the **Use SSL?** check box.
 - To enable secure communication for PDC, leave the **Use SSL?** check box selected, and in the **KeyStore Location** field, enter the path of the client-side KeyStore file generated from the exported public certificate using the **keytool** utility.

For more information, see "[Configuring SSL for the WebLogic Server Domain](#)".

20. Click **Next**.

The BRM Integration Pack Wallet Location and Password screen appears.

21. Enter the following details for the BRM Integration Pack wallet:

- a. In the **Wallet Location** field, enter the path to the directory in which the BRM Integration Pack wallet is located or is to be installed.
- b. In the **Wallet Password** field, enter the BRM Integration Pack wallet password.
- c. In the **Confirm Wallet Password** field, enter the BRM Integration Pack wallet password again.

22. Click **Next**.

The BRM Server Location screen appears.

23. Enter the BRM batch and real-time rating engine details:

- a. In the **BRM** field, enter the path to the directory in which BRM is installed.
- b. In the **BRM Pipeline** field, enter the path to the directory in which Pipeline Manager is installed.
- c. In the **Perl Home** field, enter the path to the directory in which the Perl libraries are installed.

24. Click **Next**.

The BRM Pipeline Database Connection screen appears.

25. Enter the following information required to connect to the BRM database:

- a. In the **Host Name** field, enter the IP address or the host name of the machine on which the BRM database is configured.
- b. In the **Port Number** field, enter the port number assigned to the BRM database service.

 **Note:**

If the database is SSL-enabled, enter the SSL port number in the **Port Number** field.

- c. In the **User Name** field, enter the BRM database user name.

This user should be the SYSDBA user or should have the following capabilities on the BRM database: grant create user, grant any role, grant any privileges, select any table to *username*, and grant sysdba to *username*.

- d. In the **Password** field, enter the BRM database user password.
- e. In the **Service Name** field, enter the name of the BRM database service.

 **Note:**

Ensure that the Oracle Database server is in Running state. The Installer connects to the Oracle Database server to verify the information you entered is valid.

- f. From the **SSL** list, select the type of SSL connection required for connecting to the BRM database:
 - **No**: SSL authentication is not required.
 - **Yes-One Way**: One-way SSL authentication is required. In this case, the client must authenticate the server's identity.
 - **Yes-Two Way**: Two-way SSL authentication is required. In this case, both the client and server must authenticate each others identity.
 - g. If you selected **Yes-One Way** or **Yes-Two Way**, do the following:
 - From the **Wallet Type** list, select the type of wallet to use for secure communication with the database: **SSO** or **PKCS12**.
 - In the **Truststore Wallet Location** field, enter the full path to the directory in which the database wallet is located.
 - In the **Truststore Wallet Password** field, enter the TrustStore wallet password to be used for secure communication.
 - In the **Keystore Wallet Location** field, enter the full path or browse to the directory in which the database wallet is located.
 - In the **Keystore Wallet Password** field, enter the KeyStore wallet password to be used for secure communication.
26. Click **Next**.
- The PDC Cross-Reference Schema User screen appears.
27. Do one of the following:
- If you want to create a transformation cross-reference schema user during installation, select **Yes** and proceed to step 28.
 - If you want to use an existing transformation cross-reference schema user, select **No** and proceed to step 32.
28. Click **Next**.
- The PDC Cross-Reference Database Connection screen appears.
29. Enter the following information required to connect to the PDC cross-reference database:
- a. In the **Host Name** field, enter the IP address or the host name of the machine on which to create the PDC cross-reference schema.
 - b. In the **Port Number** field, enter the port number assigned to the PDC cross-reference database service.

 **Note:**

If the database is SSL-enabled, enter the SSL port number in the **Port Number** field.

- c. In the **User Name** field, enter the PDC cross-reference database user name.
This user should be the SYSDBA user or should have the following capabilities on the PDC cross-reference database: grant create user, grant any role, grant any privileges, select any table to *username*, and grant sysdba to *username*.
- d. In the **Password** field, enter the PDC cross-reference database user password.
- e. In the **Service Name** field, enter the name of the PDC cross-reference database service.

 **Note:**

Ensure that the Oracle Database server is in Running state. The Installer connects to the Oracle Database server to verify the information you entered is valid.

- f. From the **SSL** list, select the type of SSL connection required for connecting to the PDC cross-reference database:
 - **No**: SSL authentication is not required.
 - **Yes-One Way**: One-way SSL authentication is required. In this case, the client must authenticate the server's identity.
 - **Yes-Two Way**: Two-way SSL authentication is required. In this case, both the client and server must authenticate each others identity.
 - g. If you selected **Yes-One Way** or **Yes-Two Way**, do the following:
 - From the **Wallet Type** list, select the type of wallet to use for secure communication with the database: **SSO** or **PKCS12**.
 - In the **Truststore Wallet Location** field, enter the full path to the directory in which the database wallet is located.
 - In the **Truststore Wallet Password** field, enter the TrustStore wallet password to be used for secure communication.
 - In the **Keystore Wallet Location** field, enter the full path or browse to the directory in which the database wallet is located.
 - In the **Keystore Wallet Password** field, enter the KeyStore wallet password to be used for secure communication.
30. Click **Next**.
The PDC Cross-Reference Schema screen appears.
31. Enter the following information required to create the PDC cross-reference schema and proceed to step 34:

 **Note:**

If you are migrating the pricing data from a source PDC system to a target PDC system that supports ECE, provide the details of the PDC cross-reference schema that you created for the source PDC system.

- a. In the **User Name** field, enter a PDC cross-reference schema user name.
 - b. In the **Password** field, enter a PDC cross-reference schema user password.
 - c. In the **Confirm Password** field, enter the PDC cross-reference schema user password again.
 - d. In the **PDC Tablespace** field, enter the name of the tablespace for the PDC cross-reference schema.
 - e. In the **Temp Tablespace** field, enter the name of the temporary tablespace for the PDC cross-reference schema.
32. Click **Next**.
- The PDC Cross-Reference Schema screen appears.
33. Enter the following information required to connect to the PDC cross-reference database:

 **Note:**

If you are migrating the pricing data from a source PDC system to a target PDC system that supports ECE, provide the details of the PDC cross-reference schema that you created for the source PDC system.

- a. In the **Host Name** field, enter the IP address or the host name of the machine on which to create the PDC cross-reference schema.
- b. In the **Port Number** field, enter the port number assigned to the PDC cross-reference database service.

 **Note:**

If the database is SSL-enabled, enter the SSL port number in the **Port Number** field.

- c. In the **User Name** field, enter the PDC cross-reference database user name.
This user should be the SYSDBA user or should have the following capabilities on the PDC cross-reference database: grant create user, grant any role, grant any privileges, select any table to *username*, and grant sysdba to *username*.
- d. In the **Password** field, enter the PDC cross-reference database user password.
- e. In the **Service Name** field, enter the name of the PDC cross-reference database service.

 **Note:**

Ensure that the Oracle Database server is in Running state. The Installer connects to the Oracle Database server to verify the information you entered is valid.

- f. From the **SSL** list, select the type of SSL connection required for connecting to the PDC cross-reference database:
 - **No:** SSL authentication is not required.
 - **Yes-One Way:** One-way SSL authentication is required. In this case, the client must authenticate the server's identity.
 - **Yes-Two Way:** Two-way SSL authentication is required. In this case, both the client and server must authenticate each others identity.
 - g. If you selected **Yes-One Way** or **Yes-Two Way**, do the following:
 - From the **Wallet Type** list, select the type of wallet to use for secure communication with the database: **SSO** or **PKCS12**.
 - In the **Truststore Wallet Location** field, enter the full path to the directory in which the database wallet is located.
 - In the **Truststore Wallet Password** field, enter the TrustStore wallet password to be used for secure communication.
 - In the **Keystore Wallet Location** field, enter the full path or browse to the directory in which the database wallet is located.
 - In the **Keystore Wallet Password** field, enter the KeyStore wallet password to be used for secure communication.
34. Click **Next**.
- The Pricing Design Center System User screen appears.
35. Enter the PDC user information.
- a. In the **User Name** field, enter the PDC user name.
 - b. In the **Password** field, enter the PDC user password.
36. Do one of the following:
- Click **Next**.
- The Migration Cross-Reference Database Connection screen appears.
- If you selected **Do not install Migration Utility** in step 13, proceed to step 46.
37. Enter the following information required to connect to the migration cross-reference database:
- a. In the **Host Name** field, enter the IP address or the host name of the machine on which to create the migration cross-reference database.
 - b. In the **Port Number** field, enter the port number assigned to the migration cross-reference database service.

 **Note:**

If the database is SSL-enabled, enter the SSL port number in the **Port Number** field.

- c. In the **User Name** field, enter the migration cross-reference database user name.
This user should be the SYSDBA user or should have the following capabilities on the migration cross-reference database: grant create user, grant any role, grant any privileges, select any table to *username*, and grant sysdba to *username*.
- d. In the **Password** field, enter the migration cross-reference database user password.
- e. In the **Service Name** field, enter the name of the migration cross-reference database service.

 **Note:**

Ensure that the Oracle Database server is in Running state. The Installer connects to the Oracle Database server to verify the information you entered is valid.

- f. From the **SSL** list, select the type of SSL connection required for connecting to the migration cross-reference database:
 - **No**: SSL authentication is not required.
 - **Yes-One Way**: One-way SSL authentication is required. In this case, the client must authenticate the server's identity.
 - **Yes-Two Way**: Two-way SSL authentication is required. In this case, both the client and server must authenticate each others identity.
- g. If you selected **Yes-One Way** or **Yes-Two Way**, do the following:
 - From the **Wallet Type** list, select the type of wallet to use for secure communication with the database: **SSO** or **PKCS12**.
 - In the **Truststore Wallet Location** field, enter the full path to the directory in which the database wallet is located.
 - In the **Truststore Wallet Password** field, enter the TrustStore wallet password to be used for secure communication.
 - In the **Keystore Wallet Location** field, enter the full path or browse to the directory in which the database wallet is located.
 - In the **Keystore Wallet Password** field, enter the KeyStore wallet password to be used for secure communication.

38. Click **Next**.

The Migration Cross-Reference Schema screen appears.

39. Enter the following information required to create the migration cross-reference schema in the migration cross-reference database:

- a. In the **User Name** field, enter a migration cross-reference schema user name.
- b. In the **Password** field, enter a migration cross-reference schema user password.

- c. In the **PDC Tablespace** field, enter the name of the PDC tablespace for the migration cross-reference schema.
 - d. In the **Temp Tablespace** field, enter the name of the temporary tablespace for the migration cross-reference schema.
40. Do one of the following:
 - Click **Next**.
The Migration User screen appears.
 - If you are migrating the PDC pricing data to a PDC system that supports ECE, proceed to step 42.
41. Enter the migration user details and proceed to step 46.
 - a. In the **User Name** field, enter a migration user name.
 - b. In the **Password** field, enter a migration user password.
42. Click **Next**.
The Source Migration User screen appears.
43. If you are migrating the PDC pricing data to a PDC system that supports ECE, enter the migration user details that you use to run the migration utility in the source PDC system:
 - a. In the **User Name** field, enter the migration user name.
 - b. In the **Password** field, enter the migration user password.
 - c. In the **Confirm Password** field, enter the migration user password again.
44. Click **Next**.
The Target Migration User screen appears.
45. If you are migrating the PDC pricing data to a PDC system that supports ECE, enter the migration user details that you want to use to run the migration utility in the target PDC system:
 - a. In the **User Name** field, enter the migration user name.
 - b. In the **Password** field, enter the migration user password.
 - c. In the **Confirm Password** field, enter the migration user password again.
46. Click **Next**.
The Installation Summary screen appears.
47. Review the selections you have made in the preceding screens, and click **Install**.
The Installation Progress screen appears.

 **Note:**

After the installation begins, clicking **Stop installation** stops the installation process, but the files that are already copied are not removed.

48. When the installation is done, click **Next**. The Installation Complete screen appears.

49. Click **Finish** to complete and exit.

See "[Verifying the Pricing Design Center Installation](#)" for information on verifying the successful installation of BRM Integration Pack.

See "[About Installation Logs](#)" for information on PDC Installer logs.

Installing Only PDC REST Services Manager

To install only PDC REST Services Manager:

1. Obtain the PDC software. See "[Downloading the PDC Software](#)".
2. Start the Oracle WebLogic Server domain administration server or the managed server on which you want to deploy PDC REST Services Manager, if it is not already started.
3. Ensure that the PDC database is running.
4. Go to the *temp_dir* directory, and run one of the following commands:

- To start the GUI installer:

```
Java_home/bin/java -jar pdcserver-15.0.0.0.0_generic_full.jar
```

where *Java_home* is the directory in which you installed the latest supported Java version.

- To start the GUI installer and install PDC using the **oralInventory** directory in a different location:

```
Java_home/bin/java -jar pdcserver-15.0.0.0.0_generic_full.jar -invPtrLoc  
FilePath/oraInst.loc
```

where *FilePath* is the path to the directory in which the **oralInst.loc** file is located.

- To start the GUI installer and create a silent installer response file during the installation:

```
Java_home/bin/java -jar pdcserver-15.0.0.0.0_generic_full.jar -record -  
destinationFile path
```

where *path* is the response file location and name.

The Welcome screen appears.

5. Click **Next**.

The Specify Inventory Directory and Credentials screen appears if the **oralInst.loc** file is corrupt or not present. The default location of the **oralInventory** directory is in the **/etc/oralInst.loc** file.

This screen displays the path to the default inventory directory and the default operating system group name.

6. (Optional) To change the default inventory directory details, do the following:
 - a. Enter the full path of the inventory directory.
 - b. Specify the name of the operating system group that has write permission to the inventory directory.

7. Click **Next**.

The Installation Location screen appears.

8. Enter the full path or browse to the directory in which to install PDC REST Services Manager.
9. Click **Next**.
The Installation Type screen appears.
10. Select **PDC REST Services Manager** and click **Next**.
The PDC REST Services Manager screen appears.
11. In the **Listener Port** field, enter the port number assigned to listen for API requests from the enterprise product catalog.
12. Click **Next**.
The PDC Instance Details screen appears.
13. Enter the following information required to communicate with the PDC:
 - a. In the **Host Name** field, enter the IP address or host name of the machine on which PDC is installed.
 - b. In the **Port Number** field, enter the port number of the PDC T3 service receiving product offer configurations from the PDC REST Services Manager.
 - c. In the **User Name** field, enter the PDC user name.
 - d. In the **Password** field, enter the password for the PDC user.
 - e. In the **Admin User Name** field, enter the PDC admin user name, which includes the Pricing Design Admin role.
 - f. In the **Admin Password** field, enter the password for the Admin user.
 - g. Do one of the following:
 - If you want to enable secure communication for the PDC database, leave the **Enable SSL** check box selected. This is selected by default.
 - To disable secure communication for the PDC database, deselect the **Enable SSL** check box.
14. Click **Next**.
The Installation Summary screen appears.
15. Review the selections you have made in the preceding screens, and click **Install**.
The Installation Progress screen appears.
16. When the installation is done, click **Next**.
The Installation Complete screen appears.
17. Click **Finish** to complete and exit.

You can check the log files in the *PDC_RSM_home/apps/log* directory, where *PDC_RSM_home* is the directory in which you installed PDC REST Services Manager.

You can use the *PDC_RSM_home/apps/bin/RestServicesManager.sh* control script to start, stop, restart, or check the status of PDC REST Services Manager. You can use the following arguments with the script:

- **start**: To start the REST Services Manager
- **stop**: To stop the REST Services Manager
- **restart**: To restart the REST Services Manager

- **hash** [*value*]: To encrypt passwords or sensitive information

Installing PDC in Silent Mode

Use silent install mode when you are installing PDC using the same configuration repeatedly. Silent install mode does not use the GUI and it runs in the background.

In this mode, you use a response file template that contains a predefined set of values to install PDC, BRM Integration Pack, and PDC REST Services Manager. You can generate a response file that contains the parameters and values during the PDC GUI installation.

Creating a Response File

To create a response file:

1. Create the response file by doing one of the following:
 - Create a copy of the response file that was generated during the GUI installation. See "[Installing All PDC Components](#)" for more information.

Note:

The GUI Installer does not store passwords provided during installation in the response file. You must manually add the passwords after creating a copy of the response file.

- Create a response file using the template by running the following command:

```
Java_home/bin/java -jar pdcserver-15.0.0.0.0_generic_full.jar -  
getResponseFileTemplates
```

where *Java_home* is the directory in which you installed the latest supported Java version.

The following response file is created with the default value:

oracle.communications.pdc.PricingDesignCenter.rsp. Use this file template if you are installing PDC and BRM Integration Pack.

You can create as many response files as needed.

2. Open the file in a text editor.
3. Modify the response file you copied by specifying the key-value information for the parameters you want in your installation.

Note:

- The response file template contains guidelines and examples on how to enter the values in the parameters.
- The Installer treats incorrect context, format, and type values in a response file as if no value were specified.

4. Save and close the response file.

Installing PDC in Silent Mode

To install the PDC software, BRM Integration Pack, and PDC REST Services Manager in silent mode:

1. Create the response file. See "[Creating a Response File](#)".
2. Copy the response file you created to the machine on which you run the silent installation.
3. On the machine on which you run the silent installation, go to the *temp_dir* directory to which you have downloaded the PDC server software pack, and run the following command:

```
Java_home/bin/java -jar pdcserver-15.0.0.0.0_generic_full.jar -debug -  
invPtrLoc Inventory_home/oraInventory/oraInst.loc [parameter=value] -  
responseFile path -silent
```

where:

- *Java_home* is the directory in which you installed the latest supported Java version.
- *parameter=value* is the name-value pair for an installation parameter, such as `INSTALL_TYPE=Complete`.
- *path* is the absolute path to the response file.

For example:

```
Java_home/bin/java -jar pdcserver-15.0.0.0.0_generic_full.jar -debug -  
invPtrLoc Inventory_home/oraInventory/oraInst.loc INSTALL_TYPE=Complete -  
responseFile /tmp/oracle.communications.pdc.PricingDesignCenter.rsp -silent
```

The installation runs silently in the background.

See "[Verifying the Pricing Design Center Installation](#)" for information on verifying the successful installation of PDC and BRM Integration Pack.

See "[About Installation Logs](#)" for information on the PDC Installer logs.

About Installation Logs

The installation logs are used for debugging purposes. You can check the log files in the **oraInventory/logs** directory. The default location of the **oraInventory** directory is in the **etc/oraInst.loc** file.

You use the following log files to monitor installation and postinstallation processes:

- **installActionTimeStamp.log**
- **oraInstallTimeStamp.err**
- **oraInstallTimeStamp.out**
- **dbScriptsgTimeStamp.log** (for the scripts run using SQL*Plus and JDBC)
- **silentInstallTimeStamp.log** (for silent mode installation)

where *TimeStamp* is the date and time the log file was created.

5

Pricing Design Center Postinstallation Tasks

Learn how to perform postinstallation tasks, such as creating users or synchronizing pricing setup components, after installing Oracle Communications Pricing Design Center (PDC).

Topics in this document:

- [Postinstallation Tasks for the PDC Installation](#)

Postinstallation Tasks for the PDC Installation

After installing the complete PDC software, do the following:

1. (Optional) Create additional PDC users by using Oracle WebLogic Server Administration Console. See "[Creating a PDC User](#)".
2. Add your PDC users to a group. This includes the PDC user created during the installation process as well as any additional PDC users you created in step 2. See "[Adding the PDC User to a Group](#)".
3. If you are using Elastic Charging Engine (ECE) for usage rating, install the compatible version of ECE on the machine on which ECE is installed. See "Installing Elastic Charging Engine" in *ECE Installation Guide*.
See "BRM Suite Compatibility" in *BRM Compatibility Matrix* for the compatible version of ECE.
4. Start the transformation engines. See "[Starting the Transformation Engines](#)".
5. (Optional) Restrict the tablespace quota for a schema user. The default tablespace quota is unlimited. See "[Restricting Tablespace Quota for a Schema User](#)".
6. Perform the following configuration:
 - a. Configure Oracle WebLogic Server to use the SSL-enabled data source. See "[Configuring WebLogic Server to use SSL-Enabled Data Source](#)".
 - b. Configure PDC to use the SSL-enabled data source. See "[Configuring PDC to Connect to SSL-Enabled Database](#)".
7. (Optional) Configure SAML to enable single-sign on (SSO) for PDC. See "[Setting Up Single Sign-On for Pricing Design Center](#)".
8. If you are not migrating the existing BRM pricing data to the PDC database, do the following:
 - a. Clean up the sample BRM data. See "[Cleaning up Sample BRM Data](#)".
 - b. Run the **SyncPDC** utility to synchronize the setup components defined in other BRM components with PDC. See "[Running SyncPDC](#)".
 - c. Create prerequisite setup components, such as balance elements. See "Creating Pricing Setup Components" in *PDC Creating Product Offerings* for more information. For a quick start, load sample balance element IDs and ratable usage metrics (RUMs) provided with the PDC software. See "[Loading Sample Data](#)".
 - d. Create a service-event map in PDC. See "[Creating Service-Event Maps](#)".

9. If you are using PDC REST Services Manager, do the following:
 - a. Configure the mapping of TMF priceType values to BRM event names. See "[Configuring Mapping of TMF620 priceType to BRM Event Names](#)".
 - b. Specify the base URL to return. See "[Updating the Base URL for PDC REST Services Manager](#)".

Creating a PDC User

If you want to create additional PDC users, you must create the PDC users after the installation is complete.

To create a PDC user:

1. Log in to WebLogic Server Administration Console.
2. In the **Domain Structure** section, click the **Security Realms** link.
The Summary of Security Realms page appears.
3. Click the **myrealm** link.
The Settings for myrealm page appears.
4. Click the **Users and Groups** tab.
5. Click the **Users** subtab.
6. Click **New**.
The Create a New User page appears.
7. Do the following:
 - a. In the **Name** field, enter a name for the PDC user.
 - b. (Optional) In the **Description** field, enter a brief description for the PDC user.
 - c. In the **Password** field, enter a password for the PDC user.

 **Note:**

- The PDC user password can be a maximum of 12 characters and should contain at least one non-alphabetic character.
- The user name must not be a part of the password.

- d. In the **Confirm Password** field, enter the password again.
8. Click **OK**.
The user name appears in the User table.
9. Click **Save**.

To access PDC, add the PDC user to a group based on the role of the user in the organization. See "[Adding the PDC User to a Group](#)" for more information.

Adding the PDC User to a Group

PDC is a role-based application that authenticates and authorizes users based on the group to which the user belongs. The role-based functionality of PDC is supported by the following WebLogic Server groups:

- **Pricing Design Admin:** The users belonging to this group have read and write access to the setup and pricing components.
- **Pricing Analyst:** The users belonging to this group have read access to the setup components and read and write access to the pricing components.
- **Pricing Reviewer:** The users belonging to this group have only read access to the setup and pricing components.
- **Migration Admin:** The users belonging to this group can migrate pricing data from the BRM database to the PDC database.

These groups are created by the PDC Installer during the PDC installation process. To access PDC, add the PDC user you created during the installation or after the installation is complete to a group based on the role of the user in the organization.

To add the user to the group:

1. Log in to WebLogic Server Administration Console.
2. In the **Domain Structure** section, click the **Security Realms** link.
The Summary of Security Realms page appears.
3. Click the **myrealm** link.
The Settings for myrealm page appears.
4. Click the **Users and Groups** tab.
5. Click the **Users** subtab.
6. Click the *username* link, where *username* is the name of the PDC user.
The Settings screen for *username* page appears.
7. Click the **Groups** tab.
8. In the **Parent Groups** section, from the **Available** list, select the group to which you want to assign the user.
9. Move the selected item to the **Chosen** list.
10. Click **Save**.

Starting the Transformation Engines

The transformation engines do not automatically start when you start the PDC server. You must manually start them by running the following scripts:

- For real-time rating: `BRM_Integration_Pack_home/Transformation/apps/bin/startRRETransformer`
- For batch rating: `BRM_Integration_Pack_home/Transformation/apps/bin/startBRETransformer`. This script is optional if you are using ECE for usage rating.

When you run the scripts, at the command prompt, enter the BRM Integration Pack wallet password and start the transformation engines.

Status of the Transformation Engines

If you suspect that a transformation engine has stopped running, use standard system commands to check the status of the transformation engine process.

Following are the names of the BRM transformation engine processes:

- For real-time rating:
oracle.communications.brm.pdc.server.transformation.rre.RRETransformationEngine
- For batch rating:
oracle.communications.brm.pdc.server.transformation.bre.BRETransformationEngine

Restricting Tablespace Quota for a Schema User

PDC grants unlimited tablespace quota to the following schema users:

- PDC schema
- Transformation cross-reference schema
- Migration cross-reference schema

You can restrict the quota limit for a schema user in a tablespace by using SQL*Plus.

To restrict the tablespace quota for a schema user:

1. Connect to your database using SQL*Plus:

```
sqlplus pdcUser@databaseName  
Enter password: password
```

where:

- *pdcUser* is the PDC database user name.
- *password* is the PDC database user password.
- *databaseName* is the service name or database alias of the PDC database.

2. At the SQL*Plus prompt, enter the following command:

```
SQL> alter user schema_user_name quota size on tablespace_name;
```

where:

- *schema_user_name* is the PDC schema user name.
- *size* is the tablespace quota size.
- *tablespace_name* is the name of the tablespace for the PDC schema user.

For example:

```
SQL> alter user schema_user_name quota 500k on data_ts;
```

3. Type **exit** to exit SQL*Plus.

Configuring WebLogic Server to use SSL-Enabled Data Source

You can use the Secure Sockets Layer (SSL)-enabled data source in Oracle WebLogic Server for secured communications.

You must configure WebLogic Server before configuring the data sources. For more information on configuring WebLogic Server, see the discussion about using SSL with data sources and Oracle drivers in the Oracle WebLogic Server documentation and in the following page:

<https://www.oracle.com/middleware/technologies/weblogic/configure-use-jdbcdriversssl.html>

Configuring PDC to Connect to SSL-Enabled Database

To connect to the SSL-enabled database securely for synchronizing, transforming, and migrating the PDC data, you must specify the SSL port number and the database TrustStore details in the following configuration files:

- **SyncPDCConfiguration.xml**
- **TransformationConfiguration.xml**
- **MigrationConfiguration.xml**

To connect to the SSL-enabled database:

1. Open the *BRM_Integration_Pack_home\apps\configurationfile* file.

where:

- *BRM_Integration_Pack_home* is the directory in which BRM Integration Pack is installed.
- *configurationfile* is:
 - **SyncPDCConfiguration.xml**
 - **TransformationConfiguration.xml**
 - **MigrationConfiguration.xml**

2. Uncomment the **trustStore** and **truststoreType** section to connect to the database securely:

```
<dbSSLConfiguration>
  <trustStore>databaseTruststoreLocation</trustStore>
  <trustStoreType>databaseTruststoreType</trustStoreType>
</dbSSLConfiguration>
```

where:

- *databaseTruststoreLocation* is the path to the client wallet which is used to connect to the database securely.
- *databaseTruststoreType* is the type of the trustStore used to connect to the database securely:

If *databaseTruststoreLocation* is **Wallet_Home/cwallet.sso**, the *databaseTruststoreType* is **SSO**.

If *databaseTruststoreLocation* is **Wallet_Home/ewallet.p12**, the *databaseTruststoreType* is **PKCS12**.

- Specify the SSL port number in the **connectionInfo** section for all the databases, such as the migration cross-reference database and transformation cross-reference database. For example:

```
<xrefDatabase>
<connectionInfo>
...
<port>SSL_Port</port>
...
</connectionInfo></xrefDatabase>
```

- Save and close the file.
- Go to the *BRM_Integration_Pack_home/apps/bin* directory.
- Run the following command, which updates the database TrustStore password in the BRM Integration Pack wallet:

```
./PDCBRMWalletUtil.sh walletlocation walletpassword DB_TRUSTSTORE_PASSWORD
password
```

where:

- walletlocation* is the location in which the BRM Integration Pack wallet is located.
 - walletpassword* is the BRM Integration Pack wallet password.
 - password* is the database TrustStore password.
- At the command prompt, enter **Y**.
The database **TrustStore** password is added to the BRM Integration Pack wallet.

Cleaning up Sample BRM Data

When you install BRM, its installation scripts populate sample data, including setup and pricing components. When using PDC, this data should not be initiated in BRM, but it should be defined in PDC and published to the BRM database. To ensure that PDC and BRM are integrated properly, you must clean up the BRM sample data before you start using PDC.

To clean up sample BRM data:

- Go to the *BRM_Integration_Pack_Home/apps/syncpdc/scripts* directory, where *BRM_Integration_Pack_Home* is the directory in which BRM Integration Pack is installed.
- Enter the following command, which opens SQL*Plus:

```
sqlplus brmUser@databaseName
Enter password: password
```

where:

- brmUser* is the BRM database user name.
 - password* is the BRM database user password.
 - databaseName* is the service name or database alias of the BRM database.
- Enter the following commands, which clean up BRM data:

 **Note:**

If PDC is integrated with ECE, do not run the **update_ifw_tables.sql** command.

- To clean up real-time data:

```
SQL> update_pin_tables.sql
```

- To clean up batch-rating data:

```
SQL> update_ifw_tables.sql
```

The sample BRM data is cleaned up.

4. Type **exit** to quit SQL*Plus.

If your BRM system includes a roaming pipeline, you must also perform these additional steps to clean up sample BRM data:

1. Configure a service-event map in PDC. See "Setting Up the Service-Event Map" in *PDC Creating Product Offerings*.
2. Create a charge offer in PDC that has a delayed event with a charge rate plan name as Standard. See "Configuring Charge Offers" in *PDC Creating Product Offerings*.
3. After the charge offer has been created successfully, connect to the BRM database as the pipeline user:

```
sqlplus pipelineUser@databaseName  
Enter password: password
```

where:

- *pipelineUser* is the user name for accessing the pipeline schema.
- *password* is the password for the pipeline user.
- *databaseName* is the service name or database alias of the BRM database.

4. Run the following SQL command:

```
SQL> select RATEPLAN from IFW_RATEPLAN where name like 'Standard';
```

The command returns a RATEPLAN number. Make a note of this number.

5. Make a copy of the *Pipeline_home/conf/pricingdata/Oracle/ifw_icproduct_all.sql* file.
6. In the copy of the *ifw_icproduct_all.sql* file, do the following:
 - Replace all instances of **RATEPLAN number (20001)** with the following:

```
RATEPLAN number (Number)
```

- Modify the value of ALT_RATEPLAN from NULL to *Number*.

where *Number* is the RATEPLAN number returned in step 4.

 **Note:**

Ensure that IFW_ICPRODUCT_RATE.ALT_RATEPLAN is set to a valid rate plan.

7. Run your copy of the **ifw_icproduct_all.sql** file:

```
SQL> @ifw_icproduct_all.sql
```

8. Type **exit** to quit SQL*Plus.
9. In the *Pipeline_homes/conf/roaming.reg* file, set **CarrierICRating.Module.UseRateplan** to **ALTERNATIVE**.
10. Start the roaming pipeline.

Running SyncPDC

You must run the **SyncPDC** utility to synchronize the setup components defined outside of PDC.

See "Synchronizing Pricing Setup Components" in *PDC Creating Product Offerings* for more information.

Loading Sample Data

PDC provides sample XML files to create setup components. The sample files are located in the *PDC_homes/apps/Samples/Examples* directory.

The **Examples** directory contains the following sample files:

- **PDCSampleBE.xml**. Contains all currency balance elements and some frequently used noncurrency balance elements. You can load this file to quickly create balance elements to use when configuring pricing.
- **PDCSampleRum.xml**. Contains commonly used ratable usage metrics (RUMs). You can load this file to quickly create RUMs to use when creating a service-event map and when configuring pricing.
- **OOB_ProfileSpecifications.xml**. Contains the profile attribute specifications referenced in the following custom rules: **Friends&Family**, **SpecialDay**, and **ClosedUserGroup**. This XML file references the names used in the provisioning tags provided by default with the BRM installation. See "Configuring Closed User Groups" in *PDC Creating Product Offerings*.
- **OOB_CRs.xml**. Contains the custom rules: **Friends&Family**, **SpecialDay**, and **ClosedUserGroup**. You can use these custom rules in generic and charge selectors when configuring a charge based on a subscriber's Friends & Family, Special Day, or Closed User Group profile. You must load the **OOB_ProfileSpecifications.xml** file before loading this file. See "Configuring Closed User Groups" in *PDC Creating Product Offerings*.
- **OOB_ItemTypeSelector.xml**. You must load this file if you are using ECE. This file provides the default billing item assignments that are supported by BRM without any additional configuration. See "Configuring Item Type Selectors" in *PDC Creating Product Offerings*.

 **Note:**

Before loading this file into the PDC database, make a backup copy of the customized **config_item_tags.xml** and **config_item_types.xml** files in BRM if you have created custom bill items in BRM. When you load the **OOB_ItemTypeSelector.xml** file into the PDC database, it overwrites the existing item tag-to-item type mapping in the BRM database.

You can load the sample files by using the **ImportExportPricing** utility. See "ImportExportPricing" in *PDC Creating Product Offerings* for more information.

 **Note:**

The **Examples** directory also contains sample alias files and sample pricing profile files that are provided only for reference and for use as templates for creating custom alias events or pricing profiles. You should not load the sample alias files and sample pricing profile files after installing PDC.

Creating Service-Event Maps

A service-event map defines which events can be used for a service and which RUMs can be used for each service-event combination. For example, you map the GSM Session event to the GSM service and the RUMs, Duration and Volume, to the GSM Session event.

To create a service-event map:

1. Ensure that the transformation engines are up and running.
2. Launch the PDC UI.
3. Create a service-event map by following the instructions in "Creating Service-Event Maps" in *PDC Online Help*.

Ensure that you include the following services in the service-event map:

- **TelcoGprs**
- **TelcoGsmFax**
- **TelcoGsmSms**
- **ServiceSettlementRoamingOutcollect**
- **ServiceTelcoGsmData**
- **Service (/service)**
- **ServiceIpGprs**
- **ServiceTelcoGsmTelephony**
- **ServiceSettlementRoamingIncollect**
- **ServiceWapInteractive**

Configuring Mapping of TMF620 priceType to BRM Event Names

If you are using PDC REST Services Manager, you must configure the mappings of BRM event names to the values your enterprise product catalog sends in the **priceType** property of the **ProductOfferingPrice** element of the TMF620 payload.

The mappings are configured in the **application-eventConfig.yaml** file. You can add mappings as needed for your deployment, or use the default mappings provided at installation.

To add or edit mappings:

1. Open the `PDC_RSM_home/apps/conf/application-eventConfig.yaml` file, where `PDC_RSM_home` is the directory in which you installed PDC REST Services Manager.
2. Edit the existing mappings, or use them as templates to add new ones. Use the following format:

```
pricetype : "eventname"
```

where:

- `pricetype` is the value sent in the **priceType** property of the **ProductOfferingPrice** element of the TMF620 payload
- `eventname` is the name of the BRM event the price type should be mapped to

For example, the default mappings for one-time fees and usage events are:

```
ONE_TIME : "EventBillingProductFeePurchase"  
ONE_TIME_PRICE_PLAN : "EventBillingProductFeePurchase"  
USAGE : "EventSession"  
USAGE_PRICE_PLAN : "EventSession"
```

3. Save and close the file.

You can update the mappings as your deployment needs change. After updating configuration files, always restart PDC REST Services Manager using the following command from the `PDC_RSM_home/apps/bin` directory:

```
./RestServicesManager.sh restart
```

Updating the Base URL for PDC REST Services Manager

After installing PDC REST Services Manager, update the base URL with the resource details to return in the response of PDC REST Services Manager requests. To do so, edit the `PDC_RSM_home/apps/conf/app_external.properties` file.

Note:

You don't need to restart the PDC REST Services Manager server after editing the **app_external.properties** file.

Part III

Upgrading Pricing Design Center from 12.x to 15.0

This part describes how to upgrade Oracle Communications Pricing Design Center (PDC). It contains the following chapters:

- [Pricing Design Center Pre-Upgrade Tasks](#)
- [Upgrading Pricing Design Center Software](#)
- [Pricing Design Center Post-Upgrade Tasks](#)

6

Pricing Design Center Pre-Upgrade Tasks

Learn about prerequisite tasks, such as backing up your current installation, before upgrading Oracle Communications Pricing Design Center (PDC).

Topics in this document:

- [Preinstallation Tasks for the PDC Software Upgrade](#)

Preinstallation Tasks for the PDC Software Upgrade

For information about the supported upgrade paths for PDC, see "Supported PDC Upgrades" in *BRM Compatibility Matrix*.

To upgrade PDC, do the following:

1. Shut down the current PDC instance. See "[Shutting Down the Current Instance](#)".
2. Make a complete offline backup of your existing PDC installation. See "[Backing Up the Current Installation](#)".
3. Install the compatible version of BRM on the machine on which BRM is installed.
 - See "BRM Suite Compatibility" in *BRM Compatibility Matrix* for more information about compatible versions.
 - See *BRM Installation Guide* for information about installing BRM.
4. Install the recommended version of JRE/JDK on the machine on which PDC is installed. See "[Installing JRE/JDK](#)".
5. Upgrade the PDC database.

If you have created a separate database for migration and transformation, upgrade the migration cross-reference database and the transformation cross-reference database. For instructions to upgrade the database, see the Oracle Database upgrade documentation.
6. Configure SSL for the PDC database to ensure secure communications between the PDC application and the database. See "[Configuring SSL for the PDC Database](#)".
7. If you have installed PDC and BRM Integration Pack on different machines, copy the client-side KeyStore (**client.jks**) file that you generated to the machine on which BRM Integration Pack is installed.
8. Undeploy the existing PDC installation deployed on the WebLogic Server domain. For instructions, see the discussion about undeploying applications in the Oracle WebLogic Server Administration Console Help.
9. Install the recommended version of WebLogic Server (on the machine on which PDC is installed). See "[Downloading and Installing Oracle WebLogic Server](#)".
10. Copy updated WebLogic library JARs to the appropriate location. See "[Copying Library JARs for PDC Upgrades](#)".
11. For secured communication, use an SSL-enabled data source in Oracle WebLogic Server. See "[Configuring WebLogic Server to use SSL-Enabled Data Source](#)".

12. Update the JDBC LLR Table Name. See "[Updating JDBC LLR Table Name](#)".
13. Set the JAVA_HOME environment variable. See "[Setting the JAVA_HOME Environment Variable](#)".
14. Enable JRE permissions. See "[Enabling JRE Permissions](#)".
15. Upgrade Oracle Application Development Runtime (on the machine on which PDC 11.x is installed) to the recommended version. See "[Installing Oracle Application Development Runtime](#)".
16. Enable the SSL port for the WebLogic Server domain in which the existing PDC 11.x is deployed, if it is not enabled during the WebLogic Server domain creation. See "[Enabling the SSL Port for the WebLogic Server Domain](#)".
17. Configure the minimum SSL protocol version that is enabled for SSL connection, if it is not configured during the WebLogic Server domain creation. See "[Configuring the SSL Protocol Version](#)".

Shutting Down the Current Instance

To shut down the current PDC instance:

1. Ensure that no users are logged in.
Users include customers, client applications, customer service representatives (CSRs), and so on.
2. Stop all PDC processes.
Only the PDC database instance should be running during the PDC installation or upgrade.

Backing Up the Current Installation

To prevent any data loss and minimize the impact of software or hardware failure during the upgrade, back up your existing installation.

Before installing PDC, make a complete offline backup of the following:

- The WebLogic server **domains** directory; by default, *Middleware_home1* **user_projects/domains**.
- The PDC installation directory and its content: *PDC_home*.
- The Oracle Inventory (**oralInventory**) directory. Open the */etc/oralnst.loc* file to find the default location of the **oralInventory** directory.
- The PDC database schema. See your database documentation for more information on performing full database backups.
- The transformation cross-reference database schema. See your database documentation for more information on performing full database backups.

Note:

Store this backup in a safe location. The data in these files will become necessary if you encounter any issues in the installation process.

- The migration cross-reference database schema if installed. See your database documentation for more information on performing full database backups.

Installing JRE/JDK

Install the recommended version of JRE/JDK on the machine on which you want to deploy PDC. See "PDC Software Compatibility" in *BRM Compatibility Matrix* for the recommended version of JRE/JDK.

To verify the JRE/JDK version:

1. Go to the command prompt on the machine on which you want to deploy PDC.
2. Enter the following command:

```
java -version
```

The Java version is displayed. For example:

```
java version "1.8.0_221"
```

If the version displayed does not start with **1.8.0_**, JRE/JDK 1.8 is not installed.

For information about installing JRE/JDK, see the Oracle Java documentation.

Configuring SSL for the PDC Database

You can configure secure sockets layer (SSL) for the Oracle database by creating wallets for storing certificates and then modifying the following configuration files:

- **sqlnet.ora**
- **tnsnames.ora**
- **listener.ora**

You can use the **Orapki** utility to create the wallets.

For information about configuring SSL for the Oracle database, see the Oracle Database documentation.

Downloading and Installing Oracle WebLogic Server

WebLogic Server is a component of the Oracle Fusion Middleware media pack. For the compatible version of WebLogic Server, see "PDC Software Compatibility" in *BRM Compatibility Matrix*.

For information on installing Oracle WebLogic Server and the patches (if any), see the Oracle WebLogic Server documentation on the Oracle Help Center:


<http://docs.oracle.com>

Copying Library JARs for PDC Upgrades

If you are upgrading from a previous PDC release, do the following:

1. Apply patch **p26626168_122140_Generic.zip** on top of your WebLogic Server 12.2.1.4 installation.

2. If you will be upgrading the PDC software, copy the **ojdbc8.jar** file from your Oracle database installation to the *PDC_Oracle_home/apps/lib* directory, where *PDC_Oracle_home* is the ORACLE_HOME directory for your PDC installation.
3. If you will be upgrading the BRM Integration Pack, copy the following files to the *PDC_BRM_Oracle_home/apps/lib* directory, where *PDC_BRM_Oracle_home* is the ORACLE_HOME directory for your PDC and BRM Integration Pack installation.
 - The **ojdbc8.jar** file from your Oracle database installation
 - *Middleware_home/oracle_common/modules/oracle.xdk/xmlparserv2.jar*
 - *Middleware_home/oracle_common/modules/com.sun.xml.bind.jaxb-impl.jar*
 - *Middleware_home/oracle_common/modules/com.sun.xml.bind.jaxb-core.jar*where *Middleware_home* is the ORACLE_HOME directory of your WebLogic Server installation.
4. During the PDC and BRM Integration Pack installation process, the installer will prompt you for the directory in which your prerequisite libraries are located. You will need to enter the path where you copied the JAR files.

 **Note:**

Set the prerequisite library location to the *PDC_Oracle_home/apps/lib* directory.

Configuring WebLogic Server to use SSL-Enabled Data Source

You can use the Secure Sockets Layer (SSL)-enabled data source in Oracle WebLogic Server for secured communications.

You must configure WebLogic Server before configuring the data sources. For more information on configuring WebLogic Server, see the discussion about using SSL with data sources and Oracle drivers in the Oracle WebLogic Server documentation and in the following page:

<https://www.oracle.com/middleware/technologies/weblogic/configure-use-jdbcdriverssl.html>

Updating JDBC LLR Table Name

If you are using an existing database schema during installation, the Logging Last Resource (LLR) table name must be changed to avoid errors.

To change the LLR table name:

1. Log in to WebLogic Server Administration Console.
2. In the **Domain Structure** section, expand **Environment** and select **Servers**.
The Summary of Servers page appears.
3. Select the server for which you want to change the LLR table name.
4. Click the **Configuration** tab.

5. Click the **General** subtab.
6. Click **Advanced** to show the advanced configuration options.
7. Set **JDBC LLR Table Name** to a different name.
8. Click **Save**.

For more information on LLR, see the discussion about administrative considerations and limitations for LLR data sources in the WebLogic Server documentation.

Setting the JAVA_HOME Environment Variable

Set the **JAVA_HOME** environment variable to the recommended version of JRE/JDK before running any PDC processes.

Set the **JAVA_HOME** environment variable on the machine on which you want to deploy PDC. For example, in C-shell:

1. Open the **.cshrc** file in a text editor.
2. Add or modify the following entries:

```
setenv JAVA_HOME jre/jdk_path
```

where *jre/jdk_path* is the absolute path to the directory in which JRE/JDK is installed.

For example:

```
setenv JAVA_HOME /pinhome/jre/1.8.0_144
```

3. Save and close the file.
4. Update the environment by running the following command:

```
source .cshrc
```

5. Verify the Java version by running the following command:

```
`${JAVA_HOME}/bin/java -version
```

The Java version is displayed. For example:

```
java version "1.8.0_144"Java(TM) SE Runtime Environment (build 1.8.0_144-b07)Java  
HotSpot(TM) 64-Bit Server VM (build 20.60-b01, mixed mode)
```

To set the **JAVA_HOME** environment variable for the WebLogic Server domain:

1. Go to the *Middleware_home/user_projects/domains/bin* directory, where *Middleware_home* is the directory in which the Oracle Middleware components are installed.
2. Open the **setDomain.sh** file in a text editor.
3. Add or modify the following entries before the **EXTRA_JAVA_PROPERTIES** entry:

```
JAVA_HOME="`${JAVA_HOME}`"  
export JAVA_HOME
```

4. Save and close the file.

Enabling JRE Permissions

To enable JRE permissions:

1. Go to the `jre/jdk_path/lib/security` directory.
2. Open the `java.policy` file in a text editor.
3. Add the following entries to the file:

```
grant { // JMX Java Management eXtensionspermission
    javax.management.MBeanTrustPermission "register";};
```

4. Save and close the file.

Installing Oracle Application Development Runtime

Oracle Application Development Runtime must be installed on the machine on which you will install PDC. For more information on the compatible version, see "PDC Software Compatibility" in *BRM Compatibility Matrix*.

Download Oracle Application Development Runtime from the following page:

<https://www.oracle.com/tools/downloads/application-development-framework-downloads.html>

For information on installing Oracle Application Development Runtime, see *Oracle Fusion Middleware Installation Guide* for the appropriate version.

Note:

The Oracle Fusion Middleware Application Developer Installer installs Oracle Application Development Runtime and Oracle Enterprise Manager.

Enabling the SSL Port for the WebLogic Server Domain

Before installing PDC the new version of PDC, enable the SSL port for the WebLogic Server domain in which you deployed PDC, if it is not enabled during the WebLogic Server domain creation. You must enable the SSL port even if you are not configuring SSL for the WebLogic Server domain.

To enable the SSL port for the WebLogic Server domain:

1. Start the WebLogic Server domain.
2. Log in to WebLogic Server Administration Console.
3. In the **Environment** tree, click **Servers**.
The Summary of Servers pane appears.
4. Select the server in which you want to deploy PDC.
5. Click the **Configuration** tab.
6. Click the **General** subtab.
7. Select the **SSL Listen Port Enabled** check box.
8. In the **SSL Listen Port** field, enter a free port number.
9. Click **Save**.
10. Log out of WebLogic Server Administration Console.
11. Restart the WebLogic Server domain.

See the discussion about enabling the SSL port in the Oracle WebLogic Server Administration Console Help for more information.

Configuring the SSL Protocol Version

In a production environment, Oracle recommends the TLSv1 protocol for sending and receiving messages in an SSL connection.

Note:

You need to set the same protocol version for managed servers and the administration server. Ensure that all the managed servers are down when making changes to the administration server for setting up the protocol. Oracle recommends to set the properties in the administration server and then the managed server.

To set the minimum protocol version to TLS version 1.2, specify the following as a command-line option in the WebLogic Server startup parameters:

```
-Dweblogic.security.SSL.minimumProtocolVersion=TLSv1.2
```

Note:

When you set a minimum protocol version, the TLS protocol that is enabled depend on the protocols that are configured in the SSL implementation.

See the discussion about specifying the version of the SSL protocol in the Oracle WebLogic Server documentation for more information. More information is also available in the following support article: "[WebLogic 12.2.1.x Versions That Support TLS 1.3](#)"

7

Upgrading Pricing Design Center Software

Learn how to upgrade one or more of the following Oracle Communications Pricing Design Center (PDC) components: the PDC software or Oracle Communications Billing and Revenue Management (BRM) Integration Pack.

Topics in this document:

- [About Upgrading PDC](#)
- [Upgrading PDC in GUI Mode](#)
- [Upgrading PDC in Silent Mode](#)
- [Restoring the Previous Installation](#)

About Upgrading PDC

You can upgrade PDC in GUI mode or silent mode. Upgrading PDC in silent mode lets you perform a non-interactive upgrade of PDC. You can use the silent mode to upgrade PDC quickly.

A PDC upgrade must be performed by a user who has permissions to write to the **oralinventory** directory and the *Middleware_home*/**user_projects/domains** directory, where *Middleware_home* is the directory in which the Oracle Middleware components are installed.

Upgrading PDC in GUI Mode

The steps for upgrading PDC by using the GUI depend on the PDC components you choose to upgrade:

- To upgrade both PDC and BRM Integration Pack installed on the same machine, select the **Upgrade-Complete** installation option. See "[Upgrading Both PDC and BRM Integration Pack](#)".
- To upgrade only PDC, select the **Pricing Design Center Upgrade** installation option. See "[Upgrading Only the PDC Software](#)".
- To upgrade only BRM Integration Pack, select the **BRM Integration Pack Upgrade** installation option. See "[Upgrading Only BRM Integration Pack](#)".

Upgrading Both PDC and BRM Integration Pack

To upgrade an existing PDC and BRM Integration Pack installation on the same machine:

1. Obtain the PDC software. See "[Downloading the PDC Software](#)".
2. Start the Oracle WebLogic Server domain administration server or the WebLogic Server domain managed server on which the existing PDC installation was deployed, if it is not already started.
3. Ensure that the PDC database is running.

 **Note:**

Ensure that the Oracle Database server is in Running state. The Installer connects to the Oracle Database server to verify the information you entered is valid.

4. Go to the *temp_dir* directory, and run one of the following commands:

- To start the GUI installer:

```
Java_home/bin/java -jar pdcserver-15.0.0.0.0_generic_full.jar
```

where *Java_home* is the directory in which you installed the latest supported Java version.

- To start the GUI installer and install PDC using the **oralInventory** directory in a different location:

```
Java_home/bin/java -jar pdcserver-15.0.0.0.0_generic_full.jar -invPtrLoc  
FilePath/oraInst.loc
```

where *FilePath* is the path to the directory in which the **oralnst.loc** file is located.

- To start the GUI installer and create a silent installer response file during the installation:

```
Java_home/bin/java -jar pdcserver-15.0.0.0.0_generic_full.jar -record -  
destinationFile path
```

where *path* is the response file location and name.

The Welcome screen appears.

5. Click **Next**.

The Installation Location screen appears.

6. Enter the full path or browse to the directory in which you want to install PDC and BRM Integration Pack for PDC.

 **Note:**

Ensure that you do not enter the path to the same directory in which the old version of PDC is installed. You can install the new version of PDC in a different directory on the same machine.

7. Click **Next**.

The Select Installation Type screen appears.

8. Select **Upgrade Complete** and click **Next**.

The PDC WebLogic Server screen appears.

9. Enter the following details for the WebLogic Server domain in which you want to deploy PDC:

- a. In the **Host Name** field, enter the IP address or the host name of the machine on which the WebLogic Server domain is configured.

- b. In the **Port Number** field, enter the port number assigned to the WebLogic Server domain administration server.
- c. In the **User Name** field, enter the WebLogic Server domain administrator user name.
- d. In the **Password** field, enter the WebLogic Server domain administrator user password.
- e. In the **WebLogic Home** field, enter the path to the directory in which the WebLogic Server software is installed. For example, *Middleware_home\wlserver*.
- f. To enable secure communication for PDC, select the **Enable SSL? (Recommended)** check box, and in the **KeyStore Location** field, enter the path of the client-side KeyStore file generated from the exported public certificate using the **keytool** utility. For more information, see "[Configuring SSL for the WebLogic Server Domain](#)".
- g. To allow the import and export of large XML files into PDC, select **Apply WebLogic tuning parameters**. For information about the WebLogic tuning parameters, see the installer Help.

 **Note:**

If you select this check box, you must restart the WebLogic Server domain after PDC installs successfully.

10. Click Next.

The WebLogic Server screen appears.

11. Do one of the following:

- If the existing PDC installation is deployed on the WebLogic Server domain administration server, select a WebLogic Server domain administration server from the list.
- If the existing PDC installation is deployed on the WebLogic Server domain managed server, select a WebLogic Server domain managed server from the list.

12. Enter the following details for the PDC wallet:

- a. In the **Wallet Location** field, enter the path to the directory in which the PDC wallet is located or is to be installed.
- b. In the **Wallet Password** field, enter the PDC wallet password.
- c. In the **Confirm Wallet Password** field, enter the PDC wallet password again.

13. Click Next.

The Pricing Design Center Schema screen appears.

14. Enter the following information required to connect to the PDC database:

- a. In the **Host Name** field, enter the IP address or the host name of the machine on which to create the PDC database schema.
- b. In the **Port Number** field, enter the port number assigned to the PDC database service.

 **Note:**

If the database is SSL-enabled, enter the SSL port number in the **Port Number** field.

- c. In the **User Name** field, enter the PDC database user name.
This user should be the SYSDBA user or should have the following capabilities on the PDC database: grant create user, grant any role, grant any privileges, select any table to *username*, and grant sysdba to *username*.
- d. In the **Password** field, enter the PDC database user password.
- e. In the **Service Name** field, enter the name of the PDC database service.

 **Note:**

Ensure that the Oracle Database server is in Running state. The Installer connects to the Oracle Database server to verify the information you entered is valid.

- f. From the **SSL** list, select the type of SSL connection required for connecting to the PDC database:
 - **No**: SSL authentication is not required.
 - **Yes-One Way**: One-way SSL authentication is required. In this case, the client must authenticate the server's identity.
 - **Yes-Two Way**: Two-way SSL authentication is required. In this case, both the client and server must authenticate each others identity.
- g. If you selected **Yes-One Way** or **Yes-Two Way**, do the following:
 - From the **Wallet Type** list, select the type of wallet to use for secure communication with the database: **SSO** or **PKCS12**.
 - In the **Truststore Wallet Location** field, enter the full path to the directory in which the database wallet is located.
 - In the **Truststore Wallet Password** field, enter the TrustStore wallet password to be used for secure communication.
 - In the **Keystore Wallet Location** field, enter the full path or browse to the directory in which the database wallet is located.
 - In the **Keystore Wallet Password** field, enter the KeyStore wallet password to be used for secure communication.

15. Click **Next**.

The Pricing Design Center System User screen appears.

16. Enter the existing PDC user information.

- a. In the **User Name** field, enter the name of the PDC user that you created during the PDC 11.1 or 11.2 installation.
- b. In the **Password** field, enter the password of the PDC user that you created during the PDC 11.1 or 11.2 installation.

17. Do one of the following:

- If you selected Oracle Communications Billing and Revenue Management Elastic Charging Engine (ECE) for usage rating during the PDC 11.1 or 11.2 installation, select **Elastic Charging Engine**.
- If you selected BRM real-time rating and batch rating engines for usage rating during the PDC 11.1 or 11.2 installation, select **Realtime Rating and Batch Rating Engines**.

 **Note:**

If you are using real-time and batch rating engines for usage rating, and you want to use ECE for usage rating, after the PDC upgrade, install PDC with ECE and then migrate the pricing data from the source PDC database into the target PDC database.

See the discussion about migrating PDC pricing data to PDC with ECE in *BRM Upgrade Guide*.

18. Click **Next**.

The Migration Option screen appears.

19. Do one of the following:

 **Note:**

Ensure that you select the same option that you selected during the PDC 11.1 or 11.2 installation.

- If you do not want to install the migration utility, select **Do not install Migration Utility**.
- To migrate the BRM real-time and batch rating engines pricing data to a PDC system that supports BRM real-time and batch rating engines, select **Migrate RRE and BRE Pricing Data to PDC**.
- To migrate the BRM real-time and batch rating engines pricing data to a PDC system that supports ECE, select **Migrate RRE and BRE Pricing Data to PDC with ECE**.
- To migrate the PDC pricing data to a PDC system that supports ECE, select **Migrate PDC Pricing Data to PDC with ECE**.

20. Click **Next**.

The Pricing Design Center WebLogic Server Connection screen appears.

21. Enter the WebLogic Server domain (the domain on which you deployed the existing PDC installation) information.

- a. In the **Host Name** field, enter the IP address or the host name of the machine on which the WebLogic Server domain is configured.
- b. In the **Port Number** field, enter the port number assigned to the WebLogic Server domain administration server.

 **Note:**

If you selected a WebLogic Server domain managed server in step [11](#), enter the port number to the managed server.

- c. In the **User Name** field, enter the WebLogic Server domain administrator user name.
 - d. In the **Password** field, enter the WebLogic Server domain administrator password.
 - e. In the **WebLogic Home** field, enter the path to the directory in which the WebLogic Server software is installed.
 - f. Do one of the following:
 - If you do not want to enable secure communication for PDC, deselect the **Use SSL?** check box.
 - To enable secure communication for PDC, leave the **Use SSL?** check box selected, and, in the **Keystore Location** field, enter the path of the client-side KeyStore file generated from the exported public certificate using the **keytool** utility.

For more information, see "[Configuring SSL for the WebLogic Server Domain](#)".
22. Click **Next**.
- The BRM Integration Pack Wallet Location and Password screen appears.
23. Enter the following details for the BRM Integration Pack wallet:
- a. In the **Wallet Location** field, enter the path to the directory in which the BRM Integration Pack wallet is located or is to be installed.
 - b. In the **Wallet Password** field, enter the BRM Integration Pack wallet password.
 - c. In the **Confirm Wallet Password** field, enter the BRM Integration Pack wallet password again.
24. Click **Next**.
- The BRM Server Location screen appears.
25. Enter the existing BRM batch and real-time rating engine details.
- a. In the **BRM** field, enter the path to the directory in which BRM is installed.
 - b. In the **BRM Pipeline** field, enter the path to the directory in which Pipeline Manager is installed.
 - c. In the **Perl Home** field, enter the path to the directory in which the Perl libraries are installed.
26. Click **Next**.
- The BRM Pipeline Database Connection Screen appears.
27. Enter the following information required to connect to the BRM pipeline database:
- a. In the **Host Name** field, enter the IP address or the host name of the machine on which to create the BRM pipeline database schema.

- b. In the **Port Number** field, enter the port number assigned to the BRM pipeline database service.

 **Note:**

If the database is SSL-enabled, enter the SSL port number in the **Port Number** field.

- c. In the **User Name** field, enter the BRM pipeline database user name.
This user should be the SYSDBA user or should have the following capabilities on the BRM pipeline database: grant create user, grant any role, grant any privileges, select any table to *username*, and grant sysdba to *username*.
- d. In the **Password** field, enter the BRM pipeline database user password.
- e. In the **Service Name** field, enter the name of the BRM pipeline database service.

 **Note:**

Ensure that the Oracle Database server is in Running state. The Installer connects to the Oracle Database server to verify the information you entered is valid.

- f. From the **SSL** list, select the type of SSL connection required for connecting to the BRM pipeline database:
- **No:** SSL authentication is not required.
 - **Yes-One Way:** One-way SSL authentication is required. In this case, the client must authenticate the server's identity.
 - **Yes-Two Way:** Two-way SSL authentication is required. In this case, both the client and server must authenticate each others identity.
- g. If you selected **Yes-One Way** or **Yes-Two Way**, do the following:
- From the **Wallet Type** list, select the type of wallet to use for secure communication with the database: **SSO** or **PKCS12**.
 - In the **Truststore Wallet Location** field, enter the full path to the directory in which the database wallet is located.
 - In the **Truststore Wallet Password** field, enter the TrustStore wallet password to be used for secure communication.
 - In the **Keystore Wallet Location** field, enter the full path or browse to the directory in which the database wallet is located.
 - In the **Keystore Wallet Password** field, enter the KeyStore wallet password to be used for secure communication.

28. Click **Next**.

The PDC Cross-Reference Schema screen appears.

29. Enter the following information required to connect to the PDC cross-reference database:

- a. In the **Host Name** field, enter the IP address or the host name of the machine on which to create the PDC cross-reference schema.
- b. In the **Port Number** field, enter the port number assigned to the PDC cross-reference database service.

 **Note:**

If the database is SSL-enabled, enter the SSL port number in the **Port Number** field.

- c. In the **User Name** field, enter the PDC cross-reference database user name.
This user should be the SYSDBA user or should have the following capabilities on the PDC cross-reference database: grant create user, grant any role, grant any privileges, select any table to *username*, and grant sysdba to *username*.
- d. In the **Password** field, enter the PDC cross-reference database user password.
- e. In the **Service Name** field, enter the name of the PDC cross-reference database service.

 **Note:**

Ensure that the Oracle Database server is in Running state. The Installer connects to the Oracle Database server to verify the information you entered is valid.

- f. From the **SSL** list, select the type of SSL connection required for connecting to the PDC cross-reference database:
 - **No**: SSL authentication is not required.
 - **Yes-One Way**: One-way SSL authentication is required. In this case, the client must authenticate the server's identity.
 - **Yes-Two Way**: Two-way SSL authentication is required. In this case, both the client and server must authenticate each others identity.
- g. If you selected **Yes-One Way** or **Yes-Two Way**, do the following:
 - From the **Wallet Type** list, select the type of wallet to use for secure communication with the database: **SSO** or **PKCS12**.
 - In the **Truststore Wallet Location** field, enter the full path to the directory in which the database wallet is located.
 - In the **Truststore Wallet Password** field, enter the TrustStore wallet password to be used for secure communication.
 - In the **Keystore Wallet Location** field, enter the full path or browse to the directory in which the database wallet is located.
 - In the **Keystore Wallet Password** field, enter the KeyStore wallet password to be used for secure communication.

30. Click **Next**.

The Pricing Design Center System User screen appears.

31. Enter the existing PDC user information.

- a. In the **User Name** field, enter the name of the PDC user that you created during the PDC 11.1 or 11.2 installation.
- b. In the **Password** field, enter the password of the PDC user that you created during the PDC 11.1 or 11.2 installation.

32. Click **Next**.

The Migration Cross-Reference Schema screen appears. If you selected **Do not install Migration Utility** in step 19, proceed to step 36.

33. Enter the following information required to connect to the migration cross-reference database:

- a. In the **Host Name** field, enter the IP address or the host name of the machine on which to create the migration cross-reference database schema.
- b. In the **Port Number** field, enter the port number assigned to the migration cross-reference database service.

 **Note:**

If the database is SSL-enabled, enter the SSL port number in the **Port Number** field.

c. In the **User Name** field, enter the migration cross-reference database user name.

This user should be the SYSDBA user or should have the following capabilities on the migration cross-reference database: grant create user, grant any role, grant any privileges, select any table to *username*, and grant sysdba to *username*.

- d. In the **Password** field, enter the migration cross-reference database user password.
- e. In the **Service Name** field, enter the name of the migration cross-reference database service.

 **Note:**

Ensure that the Oracle Database server is in Running state. The Installer connects to the Oracle Database server to verify the information you entered is valid.

f. From the **SSL** list, select the type of SSL connection required for connecting to the migration cross-reference database:

- **No**: SSL authentication is not required.
- **Yes-One Way**: One-way SSL authentication is required. In this case, the client must authenticate the server's identity.
- **Yes-Two Way**: Two-way SSL authentication is required. In this case, both the client and server must authenticate each others identity.

2. Start the Oracle WebLogic Server domain administration server or the WebLogic Server domain managed server on which your old version of PDC was deployed, if it is not already started.
3. Ensure that the PDC database is running.

 **Note:**

Ensure that the Oracle Database server is in Running state. The Installer connects to the Oracle Database server to verify the information you entered is valid.

4. Go to the *temp_dir* directory, and run one of the following commands:

- To start the GUI installer:

```
Java_home/bin/java -jar pdcserver-15.0.0.0.0_generic_full.jar
```

where *Java_home* is the directory in which you installed the latest supported Java version.

- To start the GUI installer and install PDC using the **oralInventory** directory in a different location:

```
Java_home/bin/java -jar pdcserver-15.0.0.0.0_generic_full.jar -invPtrLoc  
FilePath/oraInst.loc
```

where *FilePath* is the path to the directory in which the **oraInst.loc** file is located.

- To start the GUI installer and create a silent installer response file during the installation:

```
Java_home/bin/java -jar pdcserver-15.0.0.0.0_generic_full.jar -record -  
destinationFile path
```

where *path* is the response file location and name.

The Welcome screen appears.

5. Click **Next**.

The Installation Location screen appears.

6. Enter the full path or browse to the directory in which you want to install the new version of PDC.

 **Note:**

Ensure that you do not enter the path to the directory in which the old version of PDC is installed.

7. Click **Next**.

The Select Installation Type screen appears.

8. Select **Pricing Design Center Upgrade** and click **Next**.

The PDC WebLogic Server screen appears.

9. Enter the following details for the WebLogic Server domain in which you want to deploy PDC:
 - a. In the **Host Name** field, enter the IP address or the host name of the machine on which the WebLogic Server domain is configured.
 - b. In the **Port Number** field, enter the port number assigned to the WebLogic Server domain administration server.
 - c. In the **User Name** field, enter the WebLogic Server domain administrator user name.
 - d. In the **Password** field, enter the WebLogic Server domain administrator user password.
 - e. In the **WebLogic Home** field, enter the path to the directory in which the WebLogic Server software is installed. For example, *Middleware_home1\wlserver*.
 - f. To enable secure communication for PDC, select the **Enable SSL? (Recommended)** check box, and in the **KeyStore Location** field, enter the path of the client-side KeyStore file generated from the exported public certificate using the **keytool** utility.

For more information, see "[Configuring SSL for the WebLogic Server Domain](#)".
 - g. To allow the import and export of large XML files into PDC, select **Apply WebLogic tuning parameters**. For information about the WebLogic tuning parameters, see the installer Help.

 **Note:**

If you select this check box, you must restart the WebLogic Server domain after PDC installs successfully.

10. In the PDC Wallet Details screen, enter the following details for the PDC wallet:
 - a. In the **Wallet Location** field, enter the path to the directory in which the PDC wallet is located or is to be installed.
 - b. In the **Wallet Password** field, enter the PDC wallet password.
 - c. In the **Confirm Wallet Password** field, enter the PDC wallet password again.
11. Click **Next**.
The WebLogic Server screen appears.
12. Do one of the following:
 - If the existing PDC installation is deployed on the WebLogic Server domain administration server, select a WebLogic Server domain administration server from the list.
 - If the existing PDC installation is deployed on the WebLogic Server domain managed server, select a WebLogic Server domain managed server from the list.
13. Click **Next**.
The Pricing Design Center Schema screen appears.
14. Enter the following information required to connect to the PDC database:

- a. In the **Host Name** field, enter the IP address or the host name of the machine on which to create the PDC database schema.
- b. In the **Port Number** field, enter the port number assigned to the PDC database service.

 **Note:**

If the database is SSL-enabled, enter the SSL port number in the **Port Number** field.

- c. In the **User Name** field, enter the PDC database user name.
This user should be the SYSDBA user or should have the following capabilities on the PDC database: grant create user, grant any role, grant any privileges, select any table to *username*, and grant sysdba to *username*.
- d. In the **Password** field, enter the PDC database user password.
- e. In the **Service Name** field, enter the name of the PDC database service.

 **Note:**

Ensure that the Oracle Database server is in Running state. The Installer connects to the Oracle Database server to verify the information you entered is valid.

- f. From the **SSL** list, select the type of SSL connection required for connecting to the PDC database:
 - **No**: SSL authentication is not required.
 - **Yes-One Way**: One-way SSL authentication is required. In this case, the client must authenticate the server's identity.
 - **Yes-Two Way**: Two-way SSL authentication is required. In this case, both the client and server must authenticate each others identity.
- g. If you selected **Yes-One Way** or **Yes-Two Way**, do the following:
 - From the **Wallet Type** list, select the type of wallet to use for secure communication with the database: **SSO** or **PKCS12**.
 - In the **Truststore Wallet Location** field, enter the full path to the directory in which the database wallet is located.
 - In the **Truststore Wallet Password** field, enter the TrustStore wallet password to be used for secure communication.
 - In the **Keystore Wallet Location** field, enter the full path or browse to the directory in which the database wallet is located.
 - In the **Keystore Wallet Password** field, enter the KeyStore wallet password to be used for secure communication.

15. Click **Next**.

The Pricing Design Center System User screen appears.

16. Enter the existing PDC user information.
 - a. In the **User Name** field, enter the name of the PDC user that you created during the PDC 11.1 installation.
 - b. In the **Password** field, enter the password of the PDC user that you created during the PDC 11.1 installation.
 - c. In the **Confirm Password** field, enter the PDC user password again.
17. Do one of the following:
 - If you selected Oracle Communications Billing and Revenue Management Elastic Charging Engine (ECE) for usage rating during the PDC 11.1 installation, select **Elastic Charging Engine**.
 - If you selected BRM real-time rating and batch rating engines for usage rating during the PDC 11.1 installation, select **Realtime Rating and Batch Rating Engines**.

 **Note:**

If you are using real-time and batch rating engines for usage rating, and you want to use ECE for usage rating, after the PDC upgrade, install PDC with ECE and then migrate the pricing data from the source PDC database into the target PDC database.

See the discussion about migrating PDC pricing data to PDC With ECE in *BRM Upgrade Guide*.

18. Click **Next**.

The Installation Summary screen appears.
19. Review the selections you have made in the preceding screens, and click **Install**.

The Installation Progress screen appears.

 **Note:**

After the installation begins, clicking **Stop installation** stops the installation process, but the files that are already copied are not removed.

20. When the installation is done, click **Next**. The Installation Complete screen appears.

Note down the provided URL, because you will need it to access PDC.
21. Click **Finish** to complete and exit.
22. If you selected **Apply WebLogic tuning parameters**, you must restart the WebLogic Server domain.

See "[Verifying the Pricing Design Center Installation](#)" for information on verifying the successful installation of PDC.

See "[About Installation Logs](#)" for information on PDC Installer logs.

Upgrading Only BRM Integration Pack

 **Note:**

The BRM Integration Pack installation must be performed as the Linux user who installed BRM; for example, **pin_user**.

To upgrade only BRM Integration Pack:

1. Obtain the PDC software. See "[Downloading the PDC Software](#)".
2. Start the Oracle WebLogic Server domain administration server or the WebLogic Server domain managed server on which your old version of PDC was deployed, if it is not already started.
3. Verify that you are able to connect to the BRM database.
4. Go to the *temp_dir* directory, and run one of the following commands:

- To start the GUI installer:

```
Java_home/bin/java -jar pdcserver-15.0.0.0.0_generic_full.jar
```

where *Java_home* is the directory in which you installed the latest supported Java version.

- To start the GUI installer and install PDC using the **oralInventory** directory in a different location:

```
Java_home/bin/java -jar pdcserver-15.0.0.0.0_generic_full.jar -invPtrLoc  
FilePath/oraInst.loc
```

where *FilePath* is the path to the directory in which the **oraInst.loc** file is located.

- To start the GUI installer and create a silent installer response file during the installation:

```
Java_home/bin/java -jar pdcserver-15.0.0.0.0_generic_full.jar -record -  
destinationFile path
```

where *path* is the response file location and name.

The Welcome screen appears.

5. Click **Next**.

The Installation Location screen appears.

6. Enter the full path or browse to the directory in which you want to install BRM Integration Pack for the new PDC installation.

 **Note:**

Ensure that you do not enter the path to the directory in which the old version of the BRM Integration Pack for PDC is installed.

7. Click **Next**.
The Select Installation Type screen appears.
8. Select **BRM Integration Pack Upgrade** and click **Next**.
The Migration Option screen appears.
9. Do one of the following:

 **Note:**

Ensure that you select the same option that you selected during the PDC 11.1 installation.

- If you do not want to migrate data, select **Do not install Migration Utility**.
 - To migrate the BRM real-time and batch rating engines pricing data to a PDC system that supports BRM real-time and batch rating engines, select **Migrate RRE and BRE Pricing Data to PDC**.
 - To migrate the BRM real-time and batch rating engines pricing data to a PDC system that supports ECE, select **Migrate RRE and BRE Pricing Data to PDC with ECE**.
 - To migrate the PDC pricing data to a PDC system that supports ECE, select **Migrate PDC Pricing Data to PDC with ECE**.
10. Click **Next**.
The Pricing Design Center WebLogic Server Connection screen appears.
 11. Enter the WebLogic Server domain (the domain on which you deployed the existing PDC installation) information.
 - a. In the **Host Name** field, enter the IP address or the host name of the machine on which the WebLogic Server domain is configured.
 - b. In the **Port Number** field, enter the port number assigned to the WebLogic Server domain administration server.

 **Note:**

If you selected a WebLogic Server domain managed server during the PDC installation, enter the port number of the managed server.

- c. In the **User Name** field, enter the WebLogic Server domain administrator user name.
- d. In the **Password** field, enter the WebLogic Server domain administrator password.
- e. Do one of the following:
 - If you do not want to enable secure communication for PDC, deselect the **Enable SSL?** check box.
 - To enable secure communication for PDC, leave the **Enable SSL?** check box selected, and, in the **Keystore Location** field, enter the path of the

client-side KeyStore file generated from the exported public certificate using the **keytool** utility.

For more information, see "[Configuring SSL for the WebLogic Server Domain](#)".

12. Click **Next**.

The BRM Server Location screen appears.

13. Enter the existing BRM batch and real-time rating engine details.

- a. In the **BRM** field, enter the path to the directory in which BRM is installed.
- b. In the **BRM Pipeline** field, enter the path to the directory in which Pipeline Manager is installed.
- c. In the **Perl Home** field, enter the path to the directory in which the Perl libraries are installed.

14. Click **Next**.

The BRM Pipeline Database Connection screen appears.

15. Enter the following information required to connect to the BRM pipeline database:

- a. In the **Host Name** field, enter the IP address or the host name of the machine on which to create the BRM pipeline database schema.
- b. In the **Port Number** field, enter the port number assigned to the BRM pipeline database service.

 **Note:**

If the database is SSL-enabled, enter the SSL port number in the **Port Number** field.

- c. In the **User Name** field, enter the BRM pipeline database user name.

This user should be the SYSDBA user or should have the following capabilities on the BRM pipeline database: grant create user, grant any role, grant any privileges, select any table to *username*, and grant sysdba to *username*.

- d. In the **Password** field, enter the BRM pipeline database user password.
- e. In the **Service Name** field, enter the name of the BRM pipeline database service.

 **Note:**

Ensure that the Oracle Database server is in Running state. The Installer connects to the Oracle Database server to verify the information you entered is valid.

- f. From the **SSL** list, select the type of SSL connection required for connecting to the BRM pipeline database:

- **No:** SSL authentication is not required.
- **Yes-One Way:** One-way SSL authentication is required. In this case, the client must authenticate the server's identity.

- **Yes-Two Way:** Two-way SSL authentication is required. In this case, both the client and server must authenticate each others identity.
- g. If you selected **Yes-One Way** or **Yes-Two Way**, do the following:
- From the **Wallet Type** list, select the type of wallet to use for secure communication with the database: **SSO** or **PKCS12**.
 - In the **Truststore Wallet Location** field, enter the full path to the directory in which the database wallet is located.
 - In the **Truststore Wallet Password** field, enter the TrustStore wallet password to be used for secure communication.
 - In the **Keystore Wallet Location** field, enter the full path or browse to the directory in which the database wallet is located.
 - In the **Keystore Wallet Password** field, enter the KeyStore wallet password to be used for secure communication.
16. Click **Next**.
- The PDC Cross-Reference Schema screen appears.
17. Enter the following information required to connect to the PDC cross-reference database:
- a. In the **Host Name** field, enter the IP address or the host name of the machine on which to create the PDC cross-reference schema.
 - b. In the **Port Number** field, enter the port number assigned to the PDC cross-reference database service.

 **Note:**

If the database is SSL-enabled, enter the SSL port number in the **Port Number** field.

- c. In the **User Name** field, enter the PDC cross-reference database user name.
This user should be the SYSDBA user or should have the following capabilities on the PDC cross-reference database: grant create user, grant any role, grant any privileges, select any table to *username*, and grant sysdba to *username*.
- d. In the **Password** field, enter the PDC cross-reference database user password.
- e. In the **Service Name** field, enter the name of the PDC cross-reference database service.

 **Note:**

Ensure that the Oracle Database server is in Running state. The Installer connects to the Oracle Database server to verify the information you entered is valid.

- f. From the **SSL** list, select the type of SSL connection required for connecting to the PDC cross-reference database:
 - **No**: SSL authentication is not required.
 - **Yes-One Way**: One-way SSL authentication is required. In this case, the client must authenticate the server's identity.
 - **Yes-Two Way**: Two-way SSL authentication is required. In this case, both the client and server must authenticate each others identity.
 - g. If you selected **Yes-One Way** or **Yes-Two Way**, do the following:
 - From the **Wallet Type** list, select the type of wallet to use for secure communication with the database: **SSO** or **PKCS12**.
 - In the **Truststore Wallet Location** field, enter the full path to the directory in which the database wallet is located.
 - In the **Truststore Wallet Password** field, enter the TrustStore wallet password to be used for secure communication.
 - In the **Keystore Wallet Location** field, enter the full path or browse to the directory in which the database wallet is located.
 - In the **Keystore Wallet Password** field, enter the KeyStore wallet password to be used for secure communication.
18. Click **Next**.
- The Pricing Design Center System User screen appears.
19. Enter the existing PDC user information.
- a. In the **User Name** field, enter the name of the PDC user that you created during the PDC 11.1 installation.
 - b. In the **Password** field, enter the password of the PDC user that you created during the PDC 11.1 installation.
20. Click **Next**.
- The Migration Cross-Reference Schema screen appears. If you selected **Do not install Migration Utility** in step 9, proceed to step 24.
21. Enter the following information required to connect to the migration cross-reference database:
- a. In the **Host Name** field, enter the IP address or the host name of the machine on which to create the migration cross-reference database schema.
 - b. In the **Port Number** field, enter the port number assigned to the migration cross-reference database service.

 **Note:**

If the database is SSL-enabled, enter the SSL port number in the **Port Number** field.

- c. In the **User Name** field, enter the migration cross-reference database user name.

This user should be the SYSDBA user or should have the following capabilities on the migration cross-reference database: grant create user, grant any role, grant any privileges, select any table to *username*, and grant sysdba to *username*.

- d. In the **Password** field, enter the migration cross-reference database user password.
- e. In the **Service Name** field, enter the name of the migration cross-reference database service.

 **Note:**

Ensure that the Oracle Database server is in Running state. The Installer connects to the Oracle Database server to verify the information you entered is valid.

- f. From the **SSL** list, select the type of SSL connection required for connecting to the migration cross-reference database:
 - **No**: SSL authentication is not required.
 - **Yes-One Way**: One-way SSL authentication is required. In this case, the client must authenticate the server's identity.
 - **Yes-Two Way**: Two-way SSL authentication is required. In this case, both the client and server must authenticate each others identity.
 - g. If you selected **Yes-One Way** or **Yes-Two Way**, do the following:
 - From the **Wallet Type** list, select the type of wallet to use for secure communication with the database: **SSO** or **PKCS12**.
 - In the **Truststore Wallet Location** field, enter the full path to the directory in which the database wallet is located.
 - In the **Truststore Wallet Password** field, enter the TrustStore wallet password to be used for secure communication.
 - In the **Keystore Wallet Location** field, enter the full path or browse to the directory in which the database wallet is located.
 - In the **Keystore Wallet Password** field, enter the KeyStore wallet password to be used for secure communication.
22. Click **Next**.
- The Migration User screen appears.
23. Enter the migration user information.
- a. In the **User Name** field, enter the name of the migration user that you created during the PDC 11.1 installation.
 - b. In the **Password** field, enter the password of the migration user that you created during the PDC 11.1 installation.
24. Click **Next**.
- The Installation Summary screen appears.
25. Review the selections you have made in the preceding screens, and click **Install**.

The Installation Progress screen appears.

 **Note:**

After the installation begins, clicking **Stop installation** stops the installation process, but the files that are already copied are not removed.

26. When the installation is done, click **Next**. The Installation Complete screen appears.

Note down the provided URL, because you will need it to access PDC.

27. Click **Finish** to complete and exit.

See "[Verifying the Pricing Design Center Installation](#)" for information on verifying the successful installation of BRM Integration Pack.

See "[About Installation Logs](#)" for information on PDC Installer logs.

Upgrading PDC in Silent Mode

Use silent install mode when you are upgrading PDC using the same configuration repeatedly. Silent install mode does not use the GUI and it runs in the background.

In this mode, you use a response file template that contains a predefined set of values to upgrade PDC and BRM Integration Pack. You can generate a response file that contains the parameters and values during the PDC GUI installation.

Creating a Response File

To create a response file:

1. Create the response file by doing one of the following:
 - Create a copy of the response file that was generated during the GUI upgrade. See "[Upgrading Both PDC and BRM Integration Pack](#)" for more information.

 **Note:**

The GUI Installer does not store passwords provided during installation in the response file. You must manually add the passwords after creating a copy of the response file.

- Create a response file using the template by running the following command:

```
Java_home/bin/java -jar pdcserver-15.0.0.0.0_generic_full.jar -  
getResponseFileTemplates
```

where *Java_home* is the directory in which you installed the latest supported Java version.

The following response file is created with the default value:

oracle.communications.pdc.PricingDesignCenter.rsp. Use this file template if you are installing PDC and BRM Integration Pack.

You can create as many response files as needed.

2. Open the file in a text editor.
3. Modify the response file you copied by specifying the key-value information for the parameters you want in your installation.

 **Note:**

- The response file template contains guidelines and examples on how to enter the values in the parameters.
- The Installer treats incorrect context, format, and type values in a response file as if no value were specified.

4. Save and close the response file.

Upgrading PDC and BRM Integration Pack in Silent Mode

To upgrade the PDC software and BRM Integration Pack in silent mode:

1. Create the response file. See "[Creating a Response File](#)".
2. Copy the response file you created to the machine on which you run the silent installation.
3. On the machine on which you run the silent installation, go to the *temp_dir* directory to which you have downloaded the PDC server software pack, and run the following command:

```
Java_home/bin/java -jar pdcserver-15.0.0.0.0_generic_full.jar -debug -  
invPtrLoc Inventory_home/oraInventory/oraInst.loc [parameter=value] -  
responseFile path -silent
```

where:

- *Java_home* is the directory in which you installed the latest supported Java version.
- *parameter=value* is the name-value pair for an installation parameter, such as `INSTALL_TYPE=Complete`.
- *path* is the absolute path to the response file.

For example:

```
Java_home/bin/java -jar pdcserver-15.0.0.0.0_generic_full.jar -debug -  
invPtrLoc Inventory_home/oraInventory/oraInst.loc INSTALL_TYPE=Complete -  
responseFile /tmp/oracle.communications.pdc.PricingDesignCenter.rsp -silent
```

The installation runs silently in the background.

See "[Verifying the Pricing Design Center Installation](#)" for information on verifying the successful installation of PDC and BRM Integration Pack.

See "[About Installation Logs](#)" for information on the PDC Installer logs.

Restoring the Previous Installation

If your upgrade is not successful, you must restore your system to the previous installation.

To restore the previous PDC installation:

1. Restore the WebLogic server **domains** directory. Use the **domains** directory that you backed up before the upgrade to replace the following directory:

Middleware_home\user_projects\domains

2. Restore the **oralInventory** directory that you backed up before you installed the new version of PDC.
3. Restore the PDC database schema.
4. Restore the transformation cross-reference database schema.
5. Restore the migration cross-reference database schema.

8

Pricing Design Center Post-Upgrade Tasks

Learn how to perform tasks, such as creating users or synchronizing pricing setup components, after upgrading Oracle Communications Pricing Design Center (PDC).

Topics in this document:

- [Post-Upgrade Tasks for PDC](#)

Post-Upgrade Tasks for PDC

After upgrading your existing PDC installation to the new version of PDC, do the following:

1. Upgrade your PDC database schema to the new schema. See "[Upgrading the PDC Database Schema](#)".
2. If you are using Oracle Communications Billing and Revenue Management Elastic Charging Engine (ECE) for usage rating, install the compatible version of ECE on the machine on which ECE is installed.

See "BRM Suite Compatibility" in *BRM Compatibility Matrix* for more information about compatible versions.
3. Ensure that you migrate offer profiles from BRM into PDC. See "[Migrating Offer Profiles from BRM into PDC](#)".
4. Start the transformation engines. See "[Starting the Transformation Engines](#)".
5. Run the **ReplaceResourceNameWithCode.sql** upgrade script. See "[Running the BRM Integration Pack Upgrade Script](#)".
6. (Optional) Restrict the tablespace quota for a schema user. The default tablespace quota is unlimited. See "[Restricting Tablespace Quota for a Schema User](#)".
7. Perform the following configuration:
 - a. Configure PDC to use the secure sockets layer (SSL)-enabled data source. See "[Configuring WebLogic Server to use SSL-Enabled Data Source](#)".
 - b. Configure Oracle WebLogic Server to use the SSL-enabled data source. See "[Configuring PDC to Connect to SSL-Enabled Database](#)".
8. (Optional) Configure SAML to enable single-sign on (SSO) for PDC. See "[Setting Up Single Sign-On for Pricing Design Center](#)".
9. Update the following variables in the `PDC_Oracle_home/apps/bin/setEnv.sh` file:
 - MIDDLEWARE_HOME: Set this to the directory in which WebLogic Server 12.2.1.4 is installed.
 - WL_HOME: Set this to **MIDDLEWARE_HOME/wlserver**.
10. If you are not migrating the existing BRM pricing data to the PDC database, run the **SyncPDC** utility. See "[Running SyncPDC](#)".

This synchronizes the setup components defined in other BRM components with PDC.

Upgrading the PDC Database Schema

To upgrade the PDC database schema:

1. Go to the `PDC_home/server/upgrade/schema/pdc` directory.
2. Enter the following command, which opens SQL*Plus:

```
sqlplus pdcUser@databaseName
Enter password: password
```

where:

- `pdcUser` is the PDC database user name.
- `password` is the PDC database user password.
- `databaseName` is the service name or database alias of the PDC database.

3. Run the following command, which upgrades the PDC database schema:

```
SQL> @PricingDesignCenter.sql
```

4. Exit SQL*Plus.

Migrating Offer Profiles from BRM into PDC

Perform this task.

If you are using ECE for usage charging, ensure that you migrate the existing offer profile data from BRM into PDC and use only PDC for configuring policy specifications.



Note:

After you migrate the offer profile data into PDC, delete the existing offer profiles in BRM and *do not* create any new offer profiles in BRM.

To migrate offer profiles from BRM into PDC:

1. Do the following:
 - a. Replace `@PDC_SCHEMA_USER_NAME@` with the PDC schema user name in the `PDC_home/PDC/sqlscripts/policyspecification/DatabaseLinkPrivilege.jdbc` file.
 - b. Run the following command as a SYS user:

```
SQL> connect sysUser@databaseName
Enter password: password
```

```
SQL> DatabaseLinkPrivilege.jdbc
```

2. Open the `PDC_home/PDC/sqlscripts/policyspecification/PolicySpecificationDataUpgrade.sql` file in a text editor.
3. Specify the following parameters:

```
CREATE DATABASE LINK brmpdclink
CONNECT TO brm_dbhost_username
```

```
IDENTIFIED BY brm_dbhost_password
USING '(DESCRIPTION =
      (ADDRESS = (PROTOCOL = TCP) (HOST = brm_schema_hostname) (PORT =
brm_schema_port_number)))
      (CONNECT_DATA =
        (SID = brm_schema_sid)
      )
)';
```

where:

- *brm_dbhost_username* is the BRM database user name.
- *brm_dbhost_password* is the BRM database user password.
- *brm_schema_hostname* is the BRM schema host name.
- *brm_schema_port_number* is the port number assigned to the BRM schema.
- *brm_schema_sid* is the SID of the BRM schema.

4. Save and close the file.
5. Ensure that the BRM and PDC databases are running.
6. Connect to the PDC database using SQL*Plus:

```
sqlplus pdcUser@databaseName
Enter password: password
```

where:

- *pdcUser* is the PDC database user name.
- *password* is the PDC database user password.
- *databaseName* is the service name or database alias of the PDC database.

7. Migrate offer profiles into PDC by running the following command:

```
SQL> @PolicySpecificationDataUpgrade.sql
```

The offer profiles are migrated from BRM into PDC in the PDC format as policy specifications and policy labels.

8. Type **exit** to exit SQL*Plus.
9. Restart WebLogic Server.
10. Export the policy specifications and policy labels to XML files by running the following command:

```
ImportExportPricing -export FileNamePrefix -config POLICY_SPECIFICATION
ImportExportPricing -export FileNamePrefix -config POLICY_LABEL
```

where *FileNamePrefix* is the prefix to append to the beginning of the generated XML file name.

The policy specifications and policy labels are exported to the respective XML files.

11. Verify the migrated data in the XML files and make any necessary changes if required.
12. If you make any changes in the XML files, import the policy specifications and policy labels into the PDC database by running the following command:

```
ImportExportPricing -import -config POLICY_LABEL filename
ImportExportPricing -import -config POLICY_SPECIFICATION filename
```

where *filename* is the name of the XML file.

The policy specifications and policy labels are imported into the PDC database.

13. Publish the required pricing and setup components to ECE by running the following command:

```
ImportExportPricing -publish POLICY_SPECIFICATION -target ece
ImportExportPricing -publish CHARGE_OFFERING -target ece
ImportExportPricing -publish ALTERATION_OFFERING -target ece
```

The policy specifications, charge offers, and discount offers are published to ECE.

Note:

During PDC installation, the create database link privilege is granted to the PDC schema user. After migrating offer profiles from BRM into PDC, you can revoke the create database link privilege from the PDC schema user by running the following command as the SYS user:

```
sqlplus sysUser@databaseName
Enter password: password

SQL> revoke create database link from pdc_schema_hostname;
```

Starting the Transformation Engines

The transformation engines do not automatically start when you start the PDC server, you must start them manually. See the discussion about starting the transformation engines in *BRM System Administrator's Guide* for more information.

Running the BRM Integration Pack Upgrade Script

If you are using Pipeline Manager for rating, you must update the resource names in the Pipeline Manager database tables and add a column for event type in the `MIGRATE_EVENT` table by running the **ReplaceResourceNameWithCode.sql** and **MigrateEventAddEventType.sql** scripts.

To run the BRM Integration Pack upgrade scripts:

1. Make a complete offline backup of the `IFW_RESOURCE` and `IFW_PRICEMDL_STEP` tables.
2. Go to the `BRM_Integration_Pack_Home/sqlscripts/pdc_brm` directory, where `BRM_Integration_Pack_Home` is the directory in which BRM Integration Pack is installed.
3. Enter the following command, which opens SQL*Plus:

```
sqlplus systemUser@brmDBName
Enter password: password
```

where:

- *systemUser* is the SYSTEM or SYSDBA user name.
- *password* is the SYSTEM or SYSDBA user password.

- *brmDBName* is the service name or database alias of the BRM database.
4. Grant database linking privilege to the Pipeline Manager database user by running the following command:

```
SQL> GRANT CREATE DATABASE LINK TO pipelineUser;
```

where *pipelineUser* is the name of the Pipeline Manager database user.

5. Open the *BRM_Integration_Pack_Home/sqlscripts/pdc_brm/ReplaceResourceNameWithCode.sql* file in a text editor.
6. Edit the following parameters with the actual values that are used to create the database link between Pipeline Manager and the BRM database:

```
CREATE DATABASE LINK IFW_BRM_DB_LINK
CONNECT TO brm_db_user
IDENTIFIED BY brm_db_user_password
USING '(DESCRIPTION =
      (ADDRESS = (PROTOCOL = TCP) (HOST = brm_db_host) (PORT = brm_db_port))
      (CONNECT_DATA =
        (SID = brm_db_sid)
      )
)';
```

where:

- *brm_db_user* is the BRM database user name.
 - *brm_db_user_password* is the BRM database user password.
 - *brm_db_host* is the BRM schema host name.
 - *brm_db_port* is the port number assigned to the BRM schema.
 - *brm_db_sid* is the SID of the BRM schema.
7. Save and close the file.
 8. Type **exit** to exit SQL*Plus.
 9. Ensure that the BRM and Pipeline Manager databases are running:

```
sqlplus pipelineUser@pipelineDBName
Enter password: password
```

where:

- *pipelineUser* is the Pipeline database user name.
 - *password* is the Pipeline database user password.
 - *pipelineDBName* is the service name or database alias of the Pipeline database.
10. Update the resource names by running the following command:

```
SQL> @ReplaceResourceNameWithCode.sql
```

11. Add the event type column to the MIGRATE_EVENT table by running the following command:

```
SQL> @MigrateEventAddEventType.sql
```

12. Revoke the create database link privilege by running the following command as the SYSTEM or SYSDBA user:

```
SQL> REVOKE CREATE DATABASE LINK FROM pipelineUser;
```

13. Type **exit** to exit SQL*Plus.

Restricting Tablespace Quota for a Schema User

PDC grants unlimited tablespace quota to the following schema users:

- PDC schema
- Transformation cross-reference schema
- Migration cross-reference schema

You can restrict the quota limit for a schema user in a tablespace by using SQL*Plus.

To restrict the tablespace quota for a schema user:

1. Connect to your database using SQL*Plus:

```
sqlplus pdcUser@databaseName
Enter password: password
```

where:

- *pdcUser* is the PDC database user name.
- *password* is the PDC database user password.
- *databaseName* is the service name or database alias of the PDC database.

2. At the SQL*Plus prompt, enter the following command:

```
SQL> alter user schema_user_name quota size on tablespace_name;
```

where:

- *schema_user_name* is the PDC schema user name.
- *size* is the tablespace quota size.
- *tablespace_name* is the name of the tablespace for the PDC schema user.

For example:

```
SQL> alter user schema_user_name quota 500k on data_ts;
```

3. Type **exit** to exit SQL*Plus.

Configuring WebLogic Server to use SSL-Enabled Data Source

To use the SSL-enabled data source in WebLogic Server:

1. Log in to WebLogic Server Administration Console.
2. In the **Domain Structure** panel, click **Services** and **Datasources**.
The available data sources are displayed.
3. Select the following data sources for which you want to enable SSL:
 - PricingDB
 - JobDispatcherDS
 - JobDispatcherPersistentDS
4. In the **Configuration** tab, select **Connection Pool**.

5. Modify the connection URL:

```
jdbc:oracle:thin:@(DESCRIPTION=(ADDRESS=(PROTOCOL=TCPS)(HOST = hostname)(PORT = ssl-port))(CONNECT_DATA=(SERVICE_NAME=SID)))
```

where:

- *hostname* is the name of the machine on which the database is installed.
- *ssl-port* is the SSL-enabled port to use for connecting to the database.
- *SID* is the unique name of the Oracle database.

6. Add the following properties:

```
javax.net.ssl.trustStore = path to client wallet
```

```
javax.net.ssl.trustStoreType = wallet type
```

where:

- *path to client wallet* is the location of the client wallet that is used to connect to the database.
- *wallet type* is the type of the client wallet, such as SSO and PKCS12. If the extension of the client wallet is **.sso**, the *wallet type* is **SSO** and if the extension of the client wallet is **.p12**, the *wallet type* is **PKCS12**.

7. If *wallet type* is **PKCS12**, add the following property:

```
javax.net.ssl.trustStorePassword = wallet password
```

8. Restart the WebLogic Server domain.

9. Log in to the PDC application.

If you cannot log in to the PDC application, verify the WebLogic Server configurations that you have performed.

Configuring PDC to Connect to SSL-Enabled Database

To connect to the SSL-enabled database securely for synchronizing, transforming, and migrating the PDC data, you must specify the SSL port number and the database TrustStore details in the following configuration files:

- **SyncPDCConfiguration.xml**
- **TransformationConfiguration.xml**
- **MigrationConfiguration.xml**

To connect to the SSL-enabled database:

1. Open the *BRM_Integration_Pack_home\apps\configurationfile* file.

where:

- *BRM_Integration_Pack_home* is the directory in which BRM Integration Pack is installed.
- *configurationfile* is:
 - **SyncPDCConfiguration.xml**
 - **TransformationConfiguration.xml**
 - **MigrationConfiguration.xml**

2. Uncomment the **trustStore** and **truststoreType** section to connect to the database securely:

```
<dbSSLConfiguration>
  <trustStore>databaseTruststoreLocation</trustStore>
  <trustStoreType>databaseTruststoreType</trustStoreType>
</dbSSLConfiguration>
```

where:

- *databaseTruststoreLocation* is the path to the client wallet which is used to connect to the database securely.
- *databaseTruststoreType* is the type of the trustStore used to connect to the database securely:

If *databaseTruststoreLocation* is **Wallet_Home/cwallet.sso**, the *databaseTruststoreType* is **SSO**.

If *databaseTruststoreLocation* is **Wallet_Home/ewallet.p12**, the *databaseTruststoreType* is **PKCS12**.

3. Specify the SSL port number in the **connectionInfo** section for all the databases, such as the migration cross-reference database and transformation cross-reference database. For example:

```
<xrefDatabase>
<connectionInfo>
...
<port>SSL_Port</port>
...
</connectionInfo></xrefDatabase>
```

4. Save and close the file.
5. Go to the *BRM_Integration_Pack_home\apps\bin* directory.
6. Run the following command, which updates the database TrustStore password in the BRM Integration Pack wallet:

```
./PDCBRMWalletUtil.sh walletlocation walletpassword DB_TRUSTSTORE_PASSWORD
password
```

where:

- *walletlocation* is the location in which the BRM Integration Pack wallet is located.
- *walletpassword* is the BRM Integration Pack wallet password.
- *password* is the database TrustStore password.

7. At the command prompt, enter **Y**.

The database **TrustStore** password is added to the BRM Integration Pack wallet.

Running SyncPDC

You must run the **SyncPDC** utility to synchronize the setup components defined outside of PDC.

See "Synchronizing Pricing Setup Components" in *PDC Creating Product Offerings* for more information.

Part IV

Setting Up SSO for PDC

This part includes instructions for setting up single sign-on (SSO) for Oracle Communications Pricing Design Center (PDC). It contains the following chapters:

- [Setting Up Single Sign-On for Pricing Design Center](#)

9

Setting Up Single Sign-On for Pricing Design Center

Learn how to set up a single sign-on (SSO) login method for Oracle Communications Pricing Design Center (PDC) using SAML.

Topics in this document:

- [About Setting Up SSO for PDC](#)

About Setting Up SSO for PDC

SSO allows you to log in to applications using a single user name and password combination. You set up SSO for PDC by using SAML 2.0.

To implement SSO for PDC:

1. Create a SAML assertion provider. See "[Creating a SAML Assertion Provider](#)".
2. Create a SAML authenticator. See "[Creating a SAML Authenticator](#)".
3. Define SAML 2.0 general information. See "[Performing SAML 2.0 General Configurations](#)".
4. Define the SAML service provider. See "[Configuring the SAML Service Provider](#)".
5. Generate a metadata file and publish it to all SAML identity providers. See "[Publishing the Service Provider Metadata](#)".
6. Update the PDC deployment plan. See "[Updating the Deployment Plan for PDC](#)".

Creating a SAML Assertion Provider

The SAML assertion provider validates a client's identity by mapping a client-supplied token to a user name.

To create a SAML assertion provider for PDC:

1. Log in to PDC WebLogic Server Administration Console.
2. In the Domain Structure section, click the **Security Realms** link.
The Summary of Security Realms page appears.
3. Click the **myrealm** link.
The Settings for myrealm page appears.
4. Click the **Providers** tab and then click the **Authentication** subtab.
5. Click **New**.
The Create a New Authentication Provider page appears.
6. In the **Name** field, enter **samlPDC**.

7. From the **Type** list, select **SAML2IdentityAsserter**.
8. Click **OK**.
9. Activate your changes and then restart WebLogic Server.
10. Click the **Providers** tab and then click the **Authentication** subtab.
11. In the **Authentication Providers** table, click the **samlPDC** link.
The Settings for samlPDC appears.
12. Click the **Management** tab.
13. In the table under Identity Provider Partners, click **New** and then **New Web Single Sign-On Identity Provider Partner**.
14. In the Create a SAML 2.0 Web Single Sign-on Identity Provider Partner page, do the following:
 - In the **Name** field, enter **WebSSO-IdP-Partner-1**.
 - In the **Path** field, specify or browse to the full path of the metadata partner file.
 - Click **OK**.
15. In the **Identity Provider Partners** table, click **WebSSO-IdP-Partner-1**.
16. Select the **Enabled**, **Virtual User**, and **Process Attributes** checkboxes.
17. In **Redirect URIs**, enter **/pdc/***.
18. Click **Save**.
19. Verify the Identity Provider details in the **Site Info** and **Single Sign-on Signing Certificate** tabs.

Creating a SAML Authenticator

The SAML authenticator verifies the identity of users or system processes, and makes identity information available to PDC when that information is needed.

To create a SAML authenticator for PDC:

1. Log in to PDC WebLogic Server Administration Console.
2. In the Domain Structure section, click the **Security Realms** link.
The Summary of Security Realms page appears.
3. Click the **myrealm** link.
The Settings for myrealm page appears.
4. Click the **Providers** tab and then click the **Authentication** subtab.
5. Click **New**.
The Create a New Authentication Provider page appears.
6. In the **Name** field, enter **samlPDCAuth**.
7. From the **Type** list, select **SAMLAuthenticator**.
8. Click **OK**.
9. Click the **samlPDCAuth** link and then set **Control Flag** to **SUFFICIENT**.
10. Click **Save**.

11. Click the **DefaultAuthenticator** link and then set **Control Flag** to **SUFFICIENT**.
12. Click **Save**.
13. In the Settings for myrealm page, click **Reorder**.
14. Arrange the providers in the following order:
 - **samlPDCAuth**
 - **samlPDC**
 - **DefaultAuthenticator**
 - **DefaultIdentityAsserter**
15. Click **OK**.
16. In the Change Center, click **Activate Changes**.

Performing SAML 2.0 General Configurations

To perform SAML 2.0 general configurations:

1. Log in to PDC WebLogic Server Administration Console.
2. In the **Domain Structure** section, click **Environment**, **Servers**, and then **AdminServer**.
The Settings for AdminServer page appears.
3. Select **Configuration**, **Federation Services**, and then **SAML 2.0 General**.
4. In the **Site Info** section, enter the following information about your SAML 2.0 site:
 - **Published Site URL**: Enter **http://*pdc_hostname*:*port*/saml2**, where *pdc_hostname* is the PDC application host and *port* is the port on which PDC is listening on.
 - **Entity ID**: Enter **samlPDC**.
5. Click **Save**.
6. Activate your changes and then restart WebLogic Server.

Configuring the SAML Service Provider

To configure the SAML service provider:

1. Log in to PDC WebLogic Server Administration Console.
2. In the **Domain Structure** section, click **Environment**, **Servers**, and then **AdminServer**.
The Settings for AdminServer page appears.
3. Select **Configuration**, **Federation Services**, and then **SAML 2.0 Service Provider**.
4. Select the **Enabled** checkbox.
5. From the **Preferred Binding** list, select **POST**.
6. In the **Default URL** field, enter **http://*pdc_hostname*:*port*/pdcfaces/oracle/communications/brm/pdc/ui/pages/login.jspx**, where *pdc_hostname* is the PDC application host and *port* is the port on which PDC is listening on.
7. Activate your changes and then restart WebLogic Server.

Publishing the Service Provider Metadata

To publish the service provider metadata:

1. Log in to WebLogic Server Administration Console.
2. In the **Domain Structure** section, click **Environment, Servers**, and then **AdminServer**.

The Settings for AdminServer page appears.

3. Click **Configuration, Federation Services**, and then **SAML 2.0 General**.
4. Click **Publish Meta Data**.

The Publish SAML 2.0 Meta Data page appears.

5. In the **Path** field, enter the full path and name of the **spmeta.xml** file.
6. Click **OK**.

Updating the Deployment Plan for PDC

To update your deployment plan for PDC:

1. Create a new **plan.xml** file with the PDC deployment plan, or edit your existing **plan.xml** file.
2. In the file, add a **logoutURL** variable set to your identity provider (IDP) logout URL:

```
<variable-definition>
  <variable>
    <name>logoutUrl</name>
    <value>IDP_LOGOUT_URL</value>
  </variable>
</variable-definition>
```

3. Add the following **module-override** element:

```
<module-override>
  <module-name>BPA.war</module-name>
  <module-type>war</module-type>
  <module-descriptor external="false">
    <root-element>web-app</root-element>
    <uri>WEB-INF/web.xml</uri>
    <variable-assignment>
      <name>logoutUrl</name>
      <xpath>/web-app/context-param/[param-name="loginURL"]/
param-value</xpath>
      <operation>replace</operation>
    </variable-assignment>
  </module-descriptor>
</module-override>
```

4. Save and close your **plan.xml** file.
5. Redeploy the PDC application with your new **plan.xml** file.

For more information about updating and deploying your deployment plan, see the "[Create and Use a Deployment Plan in Oracle WebLogic Server](#)" tutorial.

Part V

Verifying Pricing Design Center

This part includes instructions for verifying your installation of Oracle Communications Pricing Design Center (PDC). It contains the following chapters:

- [Verifying the Pricing Design Center Installation](#)

10

Verifying the Pricing Design Center Installation

Learn how to verify that your Oracle Communications Pricing Design Center (PDC) software was installed or upgraded correctly.

Topics in this document:

- [Verifying the PDC Installation](#)
- [Verifying the BRM Integration Pack Installation](#)
- [Verifying the PDC REST Services Manager Installation](#)

Verifying the PDC Installation

You can verify that PDC is installed successfully by checking the state of all installed components or by logging in to PDC.

To check the state of all installed components:

1. Log in to the PDC domain administration server.
2. In the **Domain Structure** section, click **Deployments**.
The Summary of Deployments screen appears.
3. Ensure that all of the managed servers are running.
4. If PDC is installed successfully, the following deployments appear in an **Active** state:
 - JobDispatcher
 - PricingDesignCenter

To log in to PDC:

1. Open a browser window.
2. Enter the URL provided at the end of the installation.

 **Note:**

You can also get the URL for accessing PDC from the *PDC_home/install/readme.txt* file, where *PDC_home* is the directory in which you installed PDC.

3. Click **Go**.
The PDC login page appears.
4. Enter your user name and password.
The PDC home page appears, verifying that PDC is installed successfully.

You can also verify the PDC installation by checking the version number in the *PDC_home/apps/bin/VERSION* file.

Verifying the BRM Integration Pack Installation

By default, the installer stores sensitive information, such as account and database passwords, in the wallet, and it stores other configuration values in the respective configuration files.

You can verify that BRM Integration Pack is installed successfully by checking that the values entered during the PDC BRM Integration Pack installation are stored in the following configuration files:

- *BRM_Integration_Pack_home/apps/syncpdc/SyncPDCConfiguration.xml*
- *BRM_Integration_Pack_home/apps/transformation/TransformationConfiguration.xml*
- (If you installed the migration utility) *BRM_Integration_Pack_home/apps/migration/MigrationConfiguration.xml*

where *BRM_Integration_Pack_home* is the directory in which you installed BRM Integration Pack.

You can also verify the BRM Integration Pack installation by checking the version number in the *BRM_Integration_Pack_home/apps/bin/VERSION* file.

Verifying the PDC REST Services Manager Installation

You can verify that PDC REST Services Manager is installed successfully by checking that the values entered during the installation are stored in the following configuration files:

- *PDC_RSM_home/apps/conf/application.yaml*
- *PDC_RSM_home/apps/conf/meta-config.yaml*

where *PDC_RSM_home* is the directory in which you installed PDC REST Services Manager.

You can also verify the PDC REST Services Manager installation by checking the version number in the *PDC_RSM_home/apps/bin/VERSION* file.

Part VI

Uninstalling Pricing Design Center

This part includes instructions for uninstalling the Oracle Communications Pricing Design Center (PDC) software. It contains the following chapters:

- [Uninstalling Pricing Design Center](#)

Uninstalling Pricing Design Center

Learn how to uninstall the following Oracle Communications Pricing Design Center (PDC) components from your system: the PDC software, Oracle Communications Billing and Revenue Management (BRM) Integration Pack, and PDC REST Services Manager.

Topics in this document:

- [Uninstalling PDC in GUI Mode](#)
- [Uninstalling BRM Integration Pack in GUI Mode](#)
- [Uninstalling PDC REST Services Manager in GUI Mode](#)
- [Uninstalling PDC Using the Silent Mode](#)
- [Uninstalling BRM Integration Pack Using the Silent Mode](#)
- [Uninstalling PDC REST Services Manager Using the Silent Mode](#)

Uninstalling PDC in GUI Mode

You can use Oracle Universal Installer to uninstall PDC and its components, such as BRM Integration Pack.

Note:

Oracle Universal Installer does not uninstall an upgrade. You can restore the previous release installation by replacing the new directories using the backup copy of your previous release installation. See "[Restoring the Previous Installation](#)" for more information.

To uninstall PDC:

1. Go to the *PDC_home*/**oui/bin** directory, where *PDC_home* is the directory in which you installed PDC.
2. Clean up the WebLogic Server domain by running the following command:

```
java -cp weblogic_home/wlserver/server/lib/weblogic.jar weblogic.WLST  
cleanup_weblogic_domain.py weblogic_username weblogic_password weblogic_host  
weblogic_port weblogic_use_ssl pdg_username
```

where:

- *weblogic_home* is the directory in which WebLogic Server is installed.
- *weblogic_username* is the WebLogic Server domain administrator user name.
- *weblogic_password* is the WebLogic Server domain administrator user password.
- *weblogic_host* is the IP address or the host name of the machine on which the WebLogic Server domain is configured.

- *weblogic_port* is the port number assigned to the WebLogic Server domain administration server.
- *weblogic_use_ssl* is one of the following:
 - **true** if SSL is enabled for the WebLogic Server domain.
 - **false** if SSL is disabled for the WebLogic Server domain.
- *pdcc_username* is the name of the PDC user.

For example:

```
java -cp /home/usr/opt/Oracle/oracle_weblogic_12.2.1.4.0/wlserver/server/lib/  
weblogic.jar weblogic.WLST cleanup_weblogic_domain.py weblogic password  
hostname.com 1234 false pdccuser
```

3. Run the following command:

```
./deinstall.sh
```

The Distribution to Uninstall screen appears.

4. Select the components you want to uninstall.
5. Click **Uninstall**.

The Welcome screen appears.

6. Click **Next**.

The Uninstallation Summary screen appears.

7. Click **Uninstall**.

The Uninstallation Progress screen appears.

8. Click **Next**.

The Uninstallation Complete screen appears.

9. Click **Finish**.

The Installer removes all of the files except the log files. You must delete the log files manually.

You can check the log files in the **oralInventory/logs** directory. The default location of the **oralInventory** directory is in the **/etc/oralnst.loc** file.

Uninstalling BRM Integration Pack in GUI Mode

To uninstall BRM Integration Pack using Oracle Universal Installer:



Note:

Oracle Universal Installer does not uninstall the BRM Integration Pack upgrade. You can restore the previous release installation by replacing the new directories using the backup copy of your previous release installation. See "[Restoring the Previous Installation](#)" for more information.

1. Go to the *BRM_Integration_Pack_home/oui/bin* directory, where *BRM_Integration_Pack_home* is the directory in which you installed the BRM Integration Pack.
2. Run the following command:

```
./deinstall.sh
```

The Distribution to Uninstall screen appears.
3. Select the components you want to uninstall.
4. Click **Uninstall**.
The Welcome screen appears.
5. Click **Next**.
The Uninstallation Summary screen appears.
6. Click **Uninstall**.
The Uninstallation Progress screen appears.
7. Click **Next**.
The Uninstallation Complete screen appears.
8. Click **Finish**.

The Installer removes all of the files except the log files. You must delete the log files manually.

You can check the log files in the **oralInventory/logs** directory. The default location of the **oralInventory** directory is in the *etc/oralnst.loc* file.

Uninstalling PDC REST Services Manager in GUI Mode

To uninstall PDC REST Services Manager using Oracle Universal Installer:

1. Go to the *PDC_RSM_home/oui/bin* directory, where *PDC_RSM_home* is the directory in which you installed PDC REST Services Manager.
2. Run the following command:

```
./deinstall.sh
```

The Distribution to Uninstall screen appears.
3. Select the components you want to uninstall.
4. Click **Uninstall**.
The Welcome screen appears.
5. Click **Next**.
The Uninstallation Summary screen appears.
6. Click **Uninstall**.
The Uninstallation Progress screen appears.
7. Click **Next**.
The Uninstallation Complete screen appears.
8. Click **Finish**.

The Installer removes all of the files except the log and the configuration files. The configuration files are renamed with additional information like date and time of uninstallation. You must delete these files manually.

You can check the log files in the **oralInventory/logs** directory. The default location of the **oralInventory** directory is in the **/etc/oralnst.loc** file.

Uninstalling PDC Using the Silent Mode

To uninstall PDC using the silent mode:

1. Go to the **PDC_home/oui/bin** directory.
2. Clean up the WebLogic Server domain by running the following command:

```
java -cp Weblogic_home/wlserver/server/lib/weblogic.jar weblogic.WLST  
cleanup_weblogic_domain.py weblogic_username weblogic_password weblogic_host  
weblogic_port weblogic_use_ssl pdc_username
```

where:

- *weblogic_home* is the directory in which WebLogic Server is installed.
- *weblogic_username* is the WebLogic Server domain administrator user name.
- *weblogic_password* is the WebLogic Server domain administrator user password.
- *weblogic_host* is the IP address or the host name of the machine on which the WebLogic Server domain is configured.
- *weblogic_port* is the port number assigned to the WebLogic Server domain administration server.
- *weblogic_use_ssl* is one of the following:
 - **true** if SSL is enabled for the WebLogic Server domain.
 - **false** if SSL is disabled for the WebLogic Server domain.
- *pdc_username* is the name of the PDC user.

For example:

```
java -cp /home/usr/opt/Oracle/oracle_weblogic_12.2.1.4.0/wlserver/server/lib/  
weblogic.jar weblogic.WLST cleanup_weblogic_domain.py weblogic password  
hostname.com 1234 false pdcuser
```

3. Run the following command:

```
./deinstall.sh -silent -responseFile path
```

where *path* is the location of the response file that you created during the GUI installation of PDC.

You receive a message indicating that PDC has been uninstalled successfully.

Uninstalling BRM Integration Pack Using the Silent Mode

To uninstall BRM Integration Pack using the silent mode:

1. Go to the **BRM_Integration_Pack_home/oui/bin** directory.
2. Run the following command:

```
./deinstall.sh -silent -responseFile path
```

where *path* is the location of the response file that you created during the GUI installation of BRM Integration Pack.

You receive a message indicating that BRM Integration Pack has been uninstalled successfully.

Uninstalling PDC REST Services Manager Using the Silent Mode

To uninstall PDC REST Services Manager using the silent mode:

1. Go to the *PDC_RSM_home/oui/bin* directory.
2. Run the following command:

```
./deinstall.sh -silent -responseFile path
```

where *path* is the location of the response file that you created during the GUI installation of PDC REST Services Manager.

You receive a message indicating that PDC REST Services Manager has been uninstalled successfully.