

Oracle® Retail Predictive Application Server Cloud Service Implementation Guide



Release 25.2.301.0
G37550-02
July 2025

ORACLE®

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software, software documentation, data (as defined in the Federal Acquisition Regulation), or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs) and Oracle computer documentation or other Oracle data delivered to or accessed by U.S. Government end users are "commercial computer software," "commercial computer software documentation," or "limited rights data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, reproduction, duplication, release, display, disclosure, modification, preparation of derivative works, and/or adaptation of i) Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs), ii) Oracle computer documentation and/or iii) other Oracle data, is subject to the rights and limitations specified in the license contained in the applicable contract. The terms governing the U.S. Government's use of Oracle cloud services are defined by the applicable contract for such services. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle®, Java, MySQL, and NetSuite are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Inside are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Epyc, and the AMD logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

Contents

Send Us Your Comments

Preface

Audience	i
Documentation Accessibility	i
Related Documents	i
Customer Support	i
Improved Process for Oracle Retail Documentation Corrections	ii
Oracle Retail Documentation on the Oracle Technology Network	ii
Conventions	ii

1 Implementation

Required Skills	1
Batch Framework	1
Batch Processes Under the Control of the Implementer	2
Batch Processes Not Under the Control of the Implementer	2
POM Jobs and Batch Exec Service	2
Batch Framework Service Catalog	3
Batch Exec Service	3
Load Measure (Fact) Data: measload	4
Export Measure (Fact) Data: measexport	5
Mace Calculation Service: calc	7
Export Hierarchy: hierexport	7
Load PDS Dimension: loaddimdata	8
Load Alternate Rollup Date: altdimload	9
Batch Control Entries Required to Execute Interfaces	9
Wait for Trigger File: waittrigger	10
Send a Trigger File: sendtrigger	10
Extract Input Files from Archive: unpack	11
Transform File Service	11
Custom Function: ap_set_datr	15
Convert Informal Positions to Formal: formalize	15

Rename Positions in a Hierarchy: renamepositions	16
Workspace Refresh by Template Name: refresh	16
Workspace Rebuild by Template Name: rebuild	17
Workspace Delete by Template Name: delete	17
Run Segment Build Queue: autobuild	17
Sync Users From IDCS: idcssync	17
Shared Build (optional)	18
Configuration of interface.cfg	19
Interface Mappings	21
Syntax for Interface Mappings	22
Example for Data Importer Interface	23
Example for Data Exporter Interface	23
Example for Hierarchy/Dimension (Level) Importer Interface	24
Process for Uploading New interface.cfg File	25
Application Deploy	25
Object Storage Upload Location	26
config	26
interface.cfg (optional)	26
batch_control	26
Bootstrap Environment	26
OAT Parameters	26
Config Name	27
Partition Dim	27
Batch Group	27
Overwrite	27
Application Build	27
File Transfer Service Required Parameters	28

2 In-Context Help

Navigating to Help Topics on RPASCE	1
Creating the Contextual Help Configuration File	3
Using JSON in the Contextual Help Configuration File	3
Structure of Contextual Help Configuration File	3
Help Topic Building Block	4
Key Naming Convention	5
JSON Structure of Contextual Help Configuration File	6
Editing the Contextual Help Configuration File	6
Retrieve/Update InContext help JSON file:	7

3	Uploading and Downloading Files	
	Object Storage	1
	Accessing Endpoints to Manage Files in Object Storage	1
A	Appendix: Exit Codes	

Send Us Your Comments

Oracle Retail Cloud Edition Implementation Guide, Release 25.2.301.0.

Oracle welcomes customers' comments and suggestions on the quality and usefulness of this document.

Your feedback is important, and helps us to best meet your needs as a user of our products. For example:

- Are the implementation steps correct and complete?
- Did you understand the context of the procedures?
- Did you find any errors in the information?
- Does the structure of the information help you with your tasks?
- Do you need different information or graphics? If so, where, and in what format?
- Are the examples correct? Do you need more examples?

If you find any errors or have any other suggestions for improvement, then please tell us your name, the name of the company who has licensed our products, the title and part number of the documentation and the chapter, section, and page number (if available).

Note

Before sending us your comments, you might like to check that you have the latest version of the document and if any concerns are already addressed. To do this, access the Online Documentation available on the Oracle Technology Network Web site. It contains the most current Documentation Library plus all documents revised or released recently.

Send your comments to us using the electronic mail address: retail-doc_us@oracle.com

Please give your name, address, electronic mail address, and telephone number (optional).

If you need assistance with Oracle software, then please contact your support representative or Oracle Support Services.

If you require training or instruction in using Oracle software, then please contact your Oracle local office and inquire about our Oracle University offerings. A list of Oracle offices is available on our Web site at <http://www.oracle.com>.

Preface

Oracle Retail Implementation Guides provide detailed information useful for implementing and configuring the application. It helps you to understand the behind-the-scenes processing of the application.

Audience

This document is intended for administrators and system implementers of RPASCE.

Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc>.

Access to Oracle Support

Oracle customers that have purchased support have access to electronic support through My Oracle Support. For information, visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info> or visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs> if you are hearing impaired.

Related Documents

For more information, see the following documents in the Oracle Retail Predictive Application Server Cloud Edition documentation set:

- *Oracle Retail Predictive Application Server Cloud Edition Configuration Tools User Guide*
- *Oracle Retail Predictive Application Server Cloud Edition Release Notes*
- *Oracle Retail Predictive Application Server Cloud Edition Security Guide*
- *Oracle Retail Predictive Application Server Cloud Edition User Guide*

Customer Support

To contact Oracle Customer Support, access My Oracle Support at the following URL:

<https://support.oracle.com>

When contacting Customer Support, please provide the following:

- Product version and program/module name
- Functional and technical description of the problem (include business impact)
- Detailed step-by-step instructions to re-create
- Exact error message received

- Screen shots of each step you take

Improved Process for Oracle Retail Documentation Corrections

To more quickly address critical corrections to Oracle Retail documentation content, Oracle Retail documentation may be republished whenever a critical correction is needed. For critical corrections, the republication of an Oracle Retail document may at times not be attached to a numbered software release; instead, the Oracle Retail document will simply be replaced on the Oracle Technology Network Web site, or, in the case of Data Models, to the applicable My Oracle Support Documentation container where they reside.

Oracle Retail documentation is available on the Oracle Technology Network at the following URL:

<http://www.oracle.com/technetwork/documentation/oracle-retail-100266.html>

An updated version of the applicable Oracle Retail document is indicated by Oracle part number, as well as print date (month and year). An updated version uses the same part number, with a higher-numbered suffix. For example, part number E123456-02 is an updated version of a document with part number E123456-01.

If a more recent version of a document is available, that version supersedes all previous versions.

Oracle Retail Documentation on the Oracle Technology Network

Oracle Retail product documentation is available on the following web site:

<http://www.oracle.com/technetwork/documentation/oracle-retail-100266.html>

(Data Model documents are not available through Oracle Technology Network. You can obtain them through My Oracle Support.)

Conventions

The following text conventions are used in this document:

Convention	Meaning
boldface	Boldface type indicates graphical user interface elements associated with an action, or terms defined in text or the glossary.
<i>italic</i>	Italic type indicates book titles, emphasis, or placeholder variables for which you supply particular values.
monospace	Monospace type indicates commands within a paragraph, URLs, code in examples, text that appears on the screen, or text that you enter.

1

Implementation

RPASCE acts as a platform to create tailored solutions or migrate existing on-premise solutions into the cloud. This guide addresses the process of preparing a custom solution for use in either of these Cloud Service environments.

Because Oracle Retail Cloud Service applications do not support any back-end server access, implementation is different from an RPAS on-premise implementation. The applications provide online tools to cover all the necessary facets of an RPASCE application roll-out and administration. These include:

- Deploying and patching applications from your custom configuration
- Defining nightly, weekly, or ad hoc batch process sequences
- Scheduling recurring batch processes

Required Skills

Since implementations are based on a retailer- or implementer-provided configuration, working knowledge of the RPASCE configuration tools is essential. The RPASCE configuration tools are supported for offline use on a Windows 10 system. They are available in the applicable Starter Kits, and their use is detailed in the *Oracle Retail Predictive Application Server Cloud Edition Configuration Tools User Guide*.

In addition to supplying an RPASCE configuration, the implementer must also prepare the retailer to provide RPASCE Hierarchy (dimension) and Measure (fact) data load files, as well as to take RPASCE exported Measure (fact) data files for any downstream integration needs. While the implementer does not call the RPASCE command-line utilities directly, knowledge of their usage gained from the Oracle Retail Predictive Application Server Cloud Edition Administration Guide is helpful.

Data files for loading into the applications and exported files for integration with other systems are sent and received from the RPASCE cloud environment via Oracle Object Storage. Knowledge of the use of Object Storage File Transfer Service APIs, including an ability to automate such uploads and downloads, is a necessary prerequisite for routine nightly or weekly batch processing jobs.

Batch Framework

RPASCE operations require that the administrative user, who will not have command-line server access, must be able to select, initiate, and schedule RPASCE batch activities.

The RPASCE platform includes an Online Administration Tool (OAT) capability, which allows simple parameterization and scheduling of pre-configured batch tasks. The RPASCE provides an enhancement to the OAT framework that allows a sequence of several batch tasks to be defined. This sequence is built from a list of available batch services, such as Measure (fact) data loading, calculation, segment workspace refresh, and so on. These service tasks run in a defined order, so that you can know, for example, that your daily data updates have been loaded before your workspace refresh tasks are run. The batch tasks are configured to run under the existing OAT framework, so that scheduling them to run once, or on a repeating basis, is the same as for other OAT tasks.

The batch task sequences are defined in a small set of text files, which are specified below, with some examples.

Batch Processes Under the Control of the Implementer

Using the RPASCE batch execution framework, the following are under implementer control:

- List of batch operations to be run, with available parameterization
- Order in which batch operations are to be run
- Scheduling of one or more recurring batch tasks, which can be modified by the administrator, as needed

Batch Processes Not Under the Control of the Implementer

Due to the operational and security constraints of the Cloud Service environment, the following are not under implementer control:

- Parallelization: The applications automatically parallelize any applicable batch tasks with a number of processes set to match the provisioned server environment.
- Script file names, file and directory locations: Custom scripting is not supported for this environment, and no knowledge of file system names or locations is necessary in defining and parameterizing the batch task files.
- Incoming and outgoing file locations: These details are fixed within the RPASCE Cloud Service environment.

POM Jobs and Batch Exec Service

Process Orchestration and Monitoring (POM) is the enterprise batch-scheduling solution for retail applications migrating to the cloud. In POM, the RPASCE schedule contains multiple static jobs for each RPASCE application, namely, three daily jobs (jos_daily_pre, jos_daily, and jos_daily_post) and three weekly jobs (jos_weekly_pre, jos_weekly, and jos_weekly_post).

These jobs must exist in batch_exec_list and can map to other batch control sets for the Batch Exec Service.

For example, the following section in the batch_exec_list defines the mappings for the POM jobs.

```
# Entries for scheduling in JOS/POM
jos_daily_pre | exec | *hook_jos_daily_pre
jos_daily     | exec | batch_daily
jos_daily_post | exec | *hook_jos_daily_post
jos_weekly_pre | exec | *hook_jos_weekly_pre
jos_weekly_pre | exec | batch_weekly_pre
jos_weekly     | exec | batch_weekly
jos_weekly_post | exec | *hook_jos_weekly_post
```

In this example, the job_weekly is configured to execute the batch_weekly control set, which is a set of tasks within the batch_exec_list that can be configured in the same way as you would if not using POM. The "*" before the control set name indicates that this control set is optional, that is, if it does not exist, the batch execution of the POM job just ignores it without reporting any errors.

For more details about the RPASCE Schedule for POM, refer to the *Oracle Retail Predictive Application Server Cloud Edition Administration Guide*.

Batch Framework Service Catalog

This section describes the batch services that are available to be configured.

Batch Exec Service

The Batch Exec service is the controller for all the other services, specifying groups of tasks to be run, their sequences, and top-level parameters.

The Batch Exec service groups are specified in a text file `batch_exec_list.txt`. In this file, each active line takes this form:

```
batch_type | service | service parameter
```

The first column is an identifier, which may be repeated on several lines to define a grouping of tasks to be run together. The second column indicates which task from the catalogue is being requested. The third column gives parameter details for that task (as necessary). Comments may be placed in the `batch_exec_list.txt` file by starting a comment line with the hash sign (#).

Here is a sample `batch_exec_list.txt` file for reference:

```
# Daily Batch Cycle
daily | waittrigger | daily_upd.txt~3600
daily | unpack      | daily_upd.zip
daily | calc        | exp_set
daily | measexport  | daily_exp_set
daily | measload    | load_oo_list
daily | sendtrigger | batch_load_complete.txt~ftp
daily | calc        | batch_oo
daily | rebuild     | rebuild_daily_group
```

```
# Batch Cycle to Load OO
load_oo | measload | load_oo_list
load_oo | calc      | batch_oo
```

```
# Weekly Batch Cycle
```

```
weekly | calc      | exp_calc_set
weekly | measexport | weekly_exp_set
weekly | loaddimdata | cld~14
weekly | loaddimdata | prod~14
weekly | loaddimdata | loc~14
weekly | measload   | load_act_list
weekly | measload   | load_oo_list
weekly | calc       | batch_week
weekly | calc       | batch_fcst
weekly | refresh    | refresh_weekly
weekly | rebuild     | rebuild_weekly
weekly | autobuild   |
```

In this sample file, three batch task groups are specified: `daily`, `load_oo`, and `weekly`. Note that these names are implementer-defined identifiers; there is nothing special about the names "daily" or "weekly". Each identifier is thus associated with a sequence of tasks, which will run in the order they are listed in the file.

Note also that no information is provided about times or schedules on which these task groups should be run. Scheduling information must be specified in the RPASCE Online Administration Tool.

The services listed for each batch task group are run in the order specified when that type of batch run is requested through the OAT interface. Details on the individual batch services and what their service parameters mean are described in the following sections.

Load Measure (Fact) Data: measload

The Load Measures service allows the loading of one or several measures, the data for which may be found in one or several files. The measload service will check for the required data files in the Object Storage incoming files area. The service will optionally either validate the presence of all data files and treat this as an error condition, or treat the presence of files as optional and continue with no error if the files are not present.

Groups of measures to be loaded are specified in a control file, `batch_loadmeas_list.txt`, with the columns as follows:

- Load set name
- Parameter type, which must be one of the following:
 - H - Fact data file name
 - V - Validate option, if present, indicates missing data files are to be treated as an error condition. No third-column parameter required.
 - R - Rejected record threshold (optional). Requires third column parameter; it must be a positive integer. When this parameter is presented, the process will be stopped (error code 37) with a failure trigger when the number of rejected records exceeds the number specified. If this option is not specified, a warning trigger will be created if there are any rejected records in the measure load; however, the process will continue.
 - C - RPASCE v19 parameter, which is no longer supported.
 - M - RPASCE v19 parameter, which is no longer supported.
 - S - RPASCE v19 parameter, which is no longer supported.
- Parameter value. Relative to the parameter type specified above.

Fact Data files may contain the data for one or several facts in a comma-separated value format (CSV) with a header line.

Here is an example control file for the Load Measure service:

```
# Load Forecast Measures
load_fcst|R|200
load_fcst|V|
load_fcst|H|mp_fcst.csv.ovr
load_fcst|H|mt_fcst.csv.ovr
load_fcst|H|p_fcst.csv.ovr
load_fcst|H|lt_fcst.csv.ovr
```

In this example, if any files for the listed measures are absent, an error condition will be reported.

The Validate option checks for required data files in the internal input file directory, as well as files that have been placed in Object Storage. This allows the measload task's Validate option to correctly detect files that were previously placed in the internal input location by an unpack batch task.

When fact data files are loaded, some lines in the file may be rejected (possibly due to an incorrectly formatted input file or a position that does not exist in the dimension (level)). The RPASCE measure load process does not, by default, treat these rejected lines as errors and will continue loading any valid lines from the rest of the file. In order to detect when rejected

lines were encountered, since the batch framework does not report this as an error, the loadmeas batch task writes the rejected records count into its own log file and also creates a rejected records warning file in the outgoing area of Object Storage.

The warning file has no content, providing all relevant information in the file name itself. The file name indicates the name of the measure, the count of rejected records, and a timestamp to indicate when the task was run.

In the following example, the measure apcpfcstslsu had four rejected records when it was loaded on 26-April-2018 at 7:52am:

```
warning.eebatch_loadmeas.apcpfcstslsu.rejected.4.20180426075212
```

If the optional |R| parameter is given in the control file, the numerical value indicates a limit to the number of rejected lines, above which the rejections will be reported as an error rather than a warning. For example, in the load_fcst config shown above, the limit is given as 200. If, while loading any particular measure in this load group, more than 200 rejected record lines are detected, then the task will halt, reporting an error, and the batch sequence that includes this task will also halt. In this way, if a badly formatted or corrupted data file was uploaded, then later batch steps such as calculations or workbook refreshes will be performed.

Export Measure (Fact) Data: measexport

The Export Measures service allows the flat-file export of one or more measures, using a control file, batch_exportmeas_list.txt, to group (and parameterize) the measure lists for particular export operations. The control file allows multiple parameters to specify the details of each export group.

Here are the columns in the export control file:

- Export Set Name
- Parameter type, which must be one of the following:
 - M - Measure name, format name (optional), and output file name (optional). Separated by |. The format name is the name of the format directive specified in the measure_format_list.txt file. The output file name option is only supported when the control set is using the I parameter. If the I parameter is not specified, the output file name will be determined by the O parameter.
 - F - Filter mask measure.
 - X - Base intersection. F or X is required.
 - O - Output file name (optional). One single output file for all exported measures. This parameter is ignored if the I parameter is specified. If multiple O parameters are provided, only the first one will be used.
 - I - Flag to use an individual output file for each measure (optional). The default file name is measure_name.csv.ovr unless it is overridden by the output file name option of the parameter of M.
 - S - File share destination. Keywords: ftp, temp, cloud:<app>, where <app> is one of: ri, mfp, rdf, ap, rms. (For the rare case where multiple instances of a single RPASCE application are to be deployed, the second instance may be integrated by using the values mfp2, rdf2, or ap2.) The cloud:<app> keyword sends the output file to the indicated Oracle RGBU Cloud Service application, if configured for your environment. The temp keyword sends the output to an internal temporary location, where it will not be accessible externally but can be used by other configured batch tasks such as the transform file service (by specifying temp as the input value for the subsequent task).
 - C - Compress output. Optional; file (or files) will be compressed into .zip format.

- D - Delimiter. Optional character to use in place of a comma; to select the | character as the delimiter, specify the keyword PIPE.

Note

D simply replaces all commas with the delimiter. It does not work well with string measure values that include commas.

- U - Uppercase position name (optional). Does not have a third column option. If it is specified, the position name in the output file will be converted to an uppercase name.
- P - useDate parameter (optional). Requires either the value start or end for the third column. It is used for a measure that has a high level on the CLND hierarchy (for example, Mnth). When specified, it will replace the measure CLND level position of each data record with the lowest CLND level (for example, Day) position corresponding to that higher level position. The values start or end are used to determine whether the starting day position or the ending day position of the corresponding mnth period will be output.
- N - Specifies when to skip NA values in export (optional). Valid options for the third column are never, allna, and anyna.
 - * never - Export the corresponded data point even though the measure's values are all NA values. This option essentially exports all data points in the logical space.
 - * allna - Do not output the corresponded data point if all measure values are NA values (default mode).
 - * anyna - Do not output the corresponded data point if any one measure value is an NA value.
- T - Appends a unique identifier as suffix to the file name (optional). This generates a unique name to ensure that the parallel export can proceed. This flag can only be used with default file naming, without using the |O| flag. This flag is specifically designed to work with the intradayexport() expression.
- H - Include header line in the output file(s). Recommended if the exported data will be re-loaded into RPASCE applications at any point. By default, measure names are used in the header line. The use of the optional parameter "fact" (specified as "H | fact") causes the fact names to be used in the header line instead of the measure names.
- Parameter value. Relative to the parameter type selected above.

Here is an example control file for the Export Measure service:

```
# Export PoC Plan CP
lpcp|F|lpcpexportb
lpcp|S|ftp
lpcp|H|fact
lpcp|M|lpcpbopc
lpcp|M|lpcpbopr
lpcp|M|lpcpbopu
lpcp|M|lpcpeopc
lpcp|M|lpcpeopr
```

For the lpcp export group, the implementer has provided a Filter Mask measure, has indicated that the file will be published to the Object Storage outgoing file location (the ftp parameter naming is for compatibility with previous RPASCE versions), and has provided a list of several measures to be included in the output.

For reasons of added efficiency, the EEBatch exec specification can run a list of measexport tasks in parallel rather than consecutively. An update to the batch_exec_list.txt config file is required to make use of this capability. (No change is required in the batch_exportmeas_list.txt file.)

Instead of multiple consecutive measexport commands in the batch_exec_list.txt file, such as this:

```
daily_batch | measexport | export_sales
daily_batch | measexport | export_orders
daily_batch | measexport | export_history
```

you should specify them together on one line as a comma-separated list:

```
daily_batch | measexport | export_sales,export_orders,export_history
```

The specifications of each of those measexport tasks in the batch_exportmeas_list.txt config file stays the same; they are just all, in this case, requested to run in parallel at the batch_exec level. (This example assumes that export_sales, export_orders, and export_history are specified in the batch_exportmeas_list.txt file as described above.)

Mace Calculation Service: calc

The Calc service, which indicates that the RPASCE utility mace is to be run, uses a control file called batch_calc_list.txt. The format of this file is as follows:

```
calc_list | [group or expression] | <group name or expr text>
```

The first column provides an identifier for each group of calc instructions. These identifiers are used to select calculations to be run either directly, or as part of a Batch Exec run.

The second column must contain the keyword group or expression to indicate whether the calculation to be run is a rule group registered in the application configuration or an individual expression given in the control file itself.

The final column provides either the name of the rule group to be executed or the text of the expression to be run.

As with the other control files, any line starting with # is ignored and can be used to comment or document the file, as needed.

Here is an example file for the calculation service:

```
# Calc Set for Batch Aggregation Weekly
batch_week | group | Batch_GB
batch_week | group | Batch_AggW
batch_week | group | Batch_InvRoll
batch_week | expression | LTWPNSlsR = DRTYNSls1R+DRTYNSls2R
batch_week | expression | LTWPNSlsU = DRTYSl1U+DRTYSl2U-DRTYRtm1U-DRTYRtm2U

# Calc Set for Generating Forecast
batch_fcst | group | Batch_Fcst_G
batch_fcst | group | Batch_Fcst_L
```

Export Hierarchy: hierexport

The Export Hierarchy service allows the flat-file export of one hierarchy (dimension/levels) using a control file, batch_exporthier_list.txt, to specify available options. The format of the control file is similar to the Export Measure control file, with the exception that only one hierarchy may be specified at a time.

The three columns in the control file are:

- Export Set Name
- Parameter Type, which must be one of these options:
 - H - Hierarchy name (required)
 - T - Export type. F - only formal positions, I - only informal positions, A (or omit) - all positions
 - L - Header line export. Output file includes header line for dimension and label columns.
 - U - Export positions of user defined dimensions. This implies Header Line export mode; cannot be used with the only formal export type.
 - O - Output file name. This is optional; defaults to <hier>.dat).
 - C - Compress result file to .zip (optional)
 - S - File export destination. Keywords: ftp, cloud:<app>, where <app> is one of: ri, mfp, rdf, ap, or rms. (For the rare case where multiple instances of a single RPASCE application are to be deployed, the second instance may be integrated by using the values mfp2, rdf2, or ap2.) This sends the output file to the indicated Oracle RGBU Cloud Service application, if configured for your environment.
- Parameter value. If required, by parameter type.

Here is an example control file for the Export Hier service:

```
# Export PROD hierarchy, compressed
prod_export|H|prod
prod_export|T|F
prod_export|O|prod_exp.dat
prod_export|C|
prod_export|S|ftp
```

In this example, the prod_export grouping indicates that only the formal positions in the PROD hierarchy will be written to a compressed file prod_exp.dat.zip and placed in the Object Storage outgoing file location (the ftp parameter naming is for compatibility with previous RPASCE versions).

Load PDS Dimension: loadaddimdata

This service supports the option for loading dimension (hierarchy) data into your application from flat files. This task does not require a separate control file, but can be fully specified inside the Batch Exec (batch_exec_list.txt) control file itself.

Note that the RPAS v19 batch task hierload is now superseded by this task, and while hierload is treated as synonymous with loadaddimdata in order to preserve compatibility in batch config files brought forward from v19 deployments, note that the parameters have changed slightly from v19. The UDD option no longer exists, and must be removed from any v19 batch config files before being used in newer RPASCE versions.

The parameter column provided in the Batch Exec file contains two required values with an optional third value, separated by the ~ character. The values are: the dimension (hierarchy) to be loaded, the purgeAge value, and optionally a rejected records limit value. The rejected records limit, when specified, may be expressed as either a decimal value, indicating a percentage of records rejected, or an integer value, indicating the total number of rejected records. If this limit is exceeded, the batch task will halt with a failure condition.

This task, when run, looks for <hier>.csv.dat or <hier>.hdr.dat files in Object Storage in the path planning/incoming/input. The task also checks for planning/incoming/input/dimdata.zip, and if found, will unpack the zip file and use any relevant .dat files located in it. If no incoming data files are found, a log message will indicate this, and then the Batch process will continue without error.

Here is an example:

```
weekly | loaddimdata | prod~28~0.2
weekly | loaddimdata | loc~28~15
```

This indicates that in the weekly batch execution, the PROD hierarchy is loaded with a 28-day day purge age, and the operation will fail if more than 20% (0.2) of incoming data file records are rejected. Also, the LOC hierarchy will be loaded, with the same 28-day purge age, and in this case the operation will be failed if more than 15 records are rejected in the incoming data file.

Load Alternate Rollup Date: altdimload

This service supports the option of loading alternate rollup data for the dimension (hierarchy) into your application from flat files. This task does not require a separate control file, but can be fully specified inside the Batch Exec (batch_exec_list.txt) control file itself. The parameter column provided in the Batch Exec file contains one value that is the input file name. This file must have been uploaded into Object Storage in the path planning/<subnamespace>/incoming/input. Here is an example:

```
weekly | altdimload | scl1.csv.dat
```

This task, when run, looks for <name>.csv.dat in Object Storage in the path planning/<subnamespace>/incoming/input. If no incoming data files are found, a log message will indicate this, and then the batch process will continue without error.

Batch Control Entries Required to Execute Interfaces

The batch control framework facilitates the calling of new interfaces using the new service interface in the batch_exec_list.txt control file. Customers can update their batch control files to call the new interfaces. The interface service takes the interface name to execute as the main parameter. In addition to the interface name, it also provides two optional parameters, INTF_PROC_PARM and INTF_EXEC_PARM, using a tilde (~) as the separator. INTF_PROC_PARM can be the same <PARAM> if the customer wants to call the same interface for a subset of the parameter. If not passed, it will execute that interface for all configured parameters (PARAM) in a single call. INTF_EXEC_PARM can currently take an optional value as L to re-run the last executed interface using the same dataset. By default, each interface execution internally uses a unique RUN_ID for the dataset in the interface, and it will be marked as processed after the successful completion of the interface execution. If the interface is re-run, it will not fetch any new data unless the source system sends new data, but L as an optional parameter can be used to re-run the interface using the same RUN_ID last used.

Typical control file entries for calling multiple interfaces (both exporters and importers) within a weekly batch are shown in the following example batch_exec_list.txt file.

Example

```
batch_weekly | interface | MFP_PLAN1_EXPbatch_weekly | interface |
W_PDS_CALENDAR_Dbbatch_weekly | interface | W_PDS_SLS_IT_LC_WK_A
```

Wait for Trigger File: waittrigger

For a recurring batch task (such as a nightly or weekly batch), you can schedule the batch to run at a particular time, but you must also ensure that it will not start processing until the required input files are available. This requirement is supported by the waittrigger task. The trigger file is a temporary file that is uploaded to Object Storage under the planning/incoming path. Note that this file must be uploaded to the Object Storage last, after all the other required files are present. Note also that this trigger file will be deleted once the waittrigger task sees it, so you must not specify an actual data file as your trigger. For example, if the batch must wait for prod.dat to be present, you must specify a second file name, such as prod_dat_trigger.txt, and the external integration process that sends the latest prod.dat into the Cloud environment must also create prod_dat_trigger.txt after the prod.dat file is available.

By default, the waittrigger task waits for 23 hours for the trigger file to appear before timing out and reporting an error. A shorter timeout may optionally be specified, given in the number of seconds to wait.

The waittrigger task requires only an entry in the batch_exec_list.txt control file; no separate control file is required. Here is an example configuration for a waittrigger task:

```
daily | waittrigger | daily_upd.txt~3600
```

This example daily batch task waits up to one hour for the file daily_upd.txt to be present in the Object Storage location. The third column uses the tilde (~) character as a separator and gives two parameters values:

- the trigger file name. Simple file names only, no paths.
- (optional) number of seconds to wait before timing out

Send a Trigger File: sendtrigger

In order to notify other processes, either internal or external to the Oracle RGPU Cloud environment, of the progress of a batch task sequence, the sendtrigger task may be configured. This task takes a two parameter values, separated by the tilde (~) character. The first parameter specifies the trigger file name.

The second portion specifies the destination in which the trigger file will be created:

- ftp - writes to the Object Storage outgoing location for this application (ftp designation is for legacy compatibility with earlier RPASCE versions).
- cloud:<app> - sends the file to the Oracle RGPU Cloud Service indicated by <app>, with valid values ri, mfp, rdf, ap, or rms. (For the rare case where multiple instances of a single RPASCE application are to be deployed, the second instance may be integrated by using the values mfp2, rdf2, or ap2.)
- input - writes the file into the input directory of the current application.

The sendtrigger task requires only an entry in the batch_exec_list.txt control file; no separate control file is required. Here is an example entry for a sendtrigger task:

```
daily | sendtrigger | batch_load_complete.txt~ftp
```

This control line indicates that the file batch_load_complete.txt will be created in the Object Storage outgoing file area once batch execution successfully reaches this point in the daily batch sequence.

Note that no automatic clean-up of the trigger file is performed, so other processes that look for the presence of this trigger file must remove it. If a trigger file from the previous batch run is still in place during a subsequent batch run, the file will remain in place and the file's timestamp will be updated.

Extract Input Files from Archive: unpack

Batch tasks such as `dimdataload` or `measload` expect to find their individual `.dat` or `.ovr` files in the incoming file areas. For some integration needs, it may be preferable to send these files together in a compressed archive for faster upload and to ensure that all matching files arrive together. This integration scenario is supported by the `unpack` task. The `unpack` task may specify files with the `.zip` extension to be found in the incoming file area and unpacked into the application input directory. The archive must contain only simple file names and not any subdirectory structure, as this structure would then prevent the files from being found in the `<application>/input` directory, where later batch tasks expect them.

The daily batch example above contains this usage for the `unpack` task:

```
daily | unpack | daily_upd.zip
```

The task specifies that the archive file `daily_upd.zip` is expected to be in the incoming file area, and it will be unpacked into the application's input directory before any subsequent batch tasks are performed.

The default behavior for this task when no file is found matching the archive specification is to exit without error (batch continues). The default behavior when an archive file is found, but there is an error from unpacking the file (for example, if a malformed archive file got uploaded) is exit with an error code (batch halts).

An optional parameter is available to modify these default behaviors. If the archive file is absolutely required, and the batch must halt with an error when no archive file is found, then the required parameter value can be given:

```
daily | unpack | daily_upd.zip~required
```

If the batch must continue without errors, even when the uploaded archive file is unable to be unpacked, then the `continue` parameter can be given:

```
daily | unpack | daily_upd.zip~continue
```

Transform File Service

The Transform file service is used for simple integration capabilities for file transformations before hierarchy or measure file loads such as splitting a file, renaming file, swapping columns in the files, and so on. It also provides an option to filter file records based on particular data values. It does not call any RPASCE utilities, but instead uses some pre-defined functions that can be called and controlled by control file setting changes. It provides some powerful integration capabilities in which the user does not need to create any external process to format the files so it can readily fit into the regular batch framework. For example, a source system might send multiple measure data in a single file but the configured RPASCE solution expects individual measures per file. In such cases, users can call this service to split those files. This process can also be used to transform the exported output files into required formats that can be copied to other locations.

The parameters for this service are provided in a control file `batch_xform_list.txt`. This service can be invoked from `batch_exec_list.txt` (Batch Exec Control file) as follows:

```
<batch_set_name> | transform | <transform_set_name>
```

Here are the columns in the batch transform control file separated by the PIPE symbol (|") for the different functions that can be used.

- Transform Set Name
- Parameter Type, which must be one of the following:

Table 1-1 Transform Parameters

Parameter Type	Value
I	Input file path and valid parameter values are cloud for cloud share location (files coming in from other Oracle RGPU Cloud Services), ftp_in for SFTP input, ftp_out for SFTP output, dom_in for Dapplication input (default), dom_out (application output), temp for internal temporary ftp_dim_in for <SFTP> / rdm_input/dimdata, ftp_fact_in for <SFTP>/rdm_input/factdatadirectory, rdm_dim_in for <RDM_ROOT>/dimdata, rdm_fact_in for <RDM_ROOT>/factdata to transform interim export files.
O	Output file path, valid parameter values are: dom_in (application input directory; this is the default), dom_out (application output directory), ftp_in (SFTP input directory), ftp_out (SFTP output directory), rdm_dim_in (PDS dimension data directory), rdm_fact_in (PDS fact data directory), cloud:<app> (sends file to another Oracle RGPU Cloud Service's SFTP input directory; valid values for <app> are: ri, mfp, rdf, ap, rms; for the rare case where multiple instances of a single RPASCE application are deployed, the second instance may be integrated by using the values mfp2, rdf2, or ap2).
D	Field delimiter (default: comma), for pipe use PIPE.
E	Output file delimiter (default: comma), for pipe use PIPE.
F	Input file name (required). Can have multiple F entries, in order to merge multiple files, but at least one F entry is required.
X	Command selects only specified columns from input file and places into output file. The two required parameters (separated by "pipe" character) are: output file name and selected field numbers (a comma-separated list of columns from input file to include in the output file, but can also use Linux "cut" command format, such as 3- for third column and following, or 3-5 for third through fifth columns). Third optional argument (also separated by character) specifies a new header row for the transformed file as a comma-separated list (such as new_header1,new_header2,...). Note that if the original (input) file has a header line, the existing headers for the selected columns will be preserved, so the additional header optional argument is only required when the input file does not have a header line and one is required in the output. Multiple [X] specifiers can be given in a single transform task set, which will generate multiple separate output files.
V	Validate for files to be present.
Q	To add quotes; required if data can contain commas and the input delim is not a comma.
L	Filter file based on where filter column and filter value as parameters. By default, it equates the value; however, to use filter value as not equal to, use additional parameter as N after filter value.
U	Create unique record output files.
C	Copy a column to the end of file (copy column number).
W	Swap column from input file (column numbers to swap).
S	Sort file columns based on key columns.
A	Add a constant value at end of file.
J	Join two columns using a separator and add to the end of the file.

Table 1-1 (Cont.) Transform Parameters

Parameter Type	Value
G	To create a complete trigger output file, if needed at the end.
Z	To compress output files of a particular pattern as a zip file. It requires the following four parameters delimited by – <output_compressed_filename> – <input_files_prefix> – <input_files_extn> – <delete_compressed_files_flag (Y/N)>
M	Move or copy files of a particular pattern of files from input to output location. If M is used, only files will be moved or copied. It will not do any further processing to those files. It requires two parameters delimited by – <move_file_pattern> – delete_file_flag (Y/N) If the delete_file_flag is Y, the source is removed and the operation is a true move. If the delete_file_flag is N, it is a copy instead of a move and the source is not removed.
N	Do not push output files to cloud:<app> location at the end and still hold the files in a temporary location for further processing to compress the files before pushing the file to cloud:<app> location.
H	Add headers to transformed output file if option X is not used to transform the output file. Parameter must be the complete header for that file and is added as the first record for the output file.
Y	To delete the input files from the input directory after the transform; if not, the used input file will not be detected.
B	Do not merge input files by file name pattern. By default, this task takes all input files with same pattern and merges them. For example, if the input file name is given as sls.csv.ovr, it will merge all files matching sls.csv.ovr*. This option indicates that only the single input file by the exact name must be used.
P	Add a timestamp to output file(s). When specified, output file names will be appended with _YYYYMMDDHHMMSS timestamp. If multiple files are produced by the same Transform task, the timestamp values will all be the same (other parts of the file names being different).

- Parameter Values - Relative to the parameter type selected above.

Example 1: To split a single file into multiple files based on column IDs.

```
rms_oo|F|rms_oo.csv.ovr
rms_oo|I|cloud
rms_oo|V|
rms_oo|X|drtyoou.csv.rpl|1,2,3,6
rms_oo|X|drtyooc.csv.rpl|1,2,3,7
rms_oo|X|drtyoor.csv.rpl|1,2,3,8
```

This example shows an input file split into multiple files using the multiple X option based on column numbers. In the above example, the output files are created in the application input directory.

Example 2: To split a single file into multiple files based on column IDs and also to filter records based on a column value.

```
rms_inv1|F|rms_inv.csv.ovr
rms_inv1|I|cloud
rms_inv1|V| rms_inv1|L|5|N
rms_inv1|X|drtyeop1u.csv.ovr|1,2,3,6
```

```
rms_inv1|X|drtyeop1c.csv.ovr|1,2,3,7
rms_inv1|X|drtyeop1r.csv.ovr|1,2,3,8
```

In this example, the first only records with fifth column value as N in the csv file and then those will split into multiple files.

Example 3: To copy columns and swap columns before writing the output file.

```
rms_curh|F|rms_curr.csv.ovr
rms_curh|I|cloud
rms_curh|C|3
rms_curh|W|2|6
rms_curh|U|
rms_curh|X|curh.csv.dat|2,3
```

In this example, the original file only contains five columns. The third column is copied to the end of the file as the sixth column due to the use of option C. Then, columns 2 and 6 are swapped due to the use of option W. Then it writes out column 2,3 after removing duplicates due to use of option U.

Example 4: To add a constant value to a file and to join two columns based on a separator.

```
rms_patt3|F|rms_prod.csv.dat
rms_patt3|I|cloud
rms_patt3|L|22|NA|N
rms_patt3|A|BRAND
rms_patt3|J|34|22|_
rms_patt3|X|drdvprdat.csv.ovr.3|1,34,35
```

It is necessary to add a constant value BRAND and also concatenate it with another column and export both the columns.

In this example, the original file only contains 33 columns. It is first filtered for records not equal to NA in column 22. Then it adds a constant value BRAND in column 34. Then, columns 34 and 22 are joined, using the separator _ (underscore) that is added as column 35. Finally, the newly added columns 34 and 35 are extracted into an output file.

Example 5: The following sample shows the use of E to create different delimited output file and Z option to compress the output file.

```
mfp_exp_ri|F|ri_mpop_plan.dat
mfp_exp_ri|F|ri_mpcp_plan.dat
mfp_exp_ri|I|temp mfp_exp_ri|V|
mfp_exp_ri|X|W_RTL_PLAN1_PROD1_LC1_T1_FS.dat|4-
mfp_exp_ri|O|cloud:ri mfp_exp_ri|E|PIPE
mfp_exp_ri|Z|RI_MFP_DATA|W_RTL_PLAN|dat|Y
```

In this example, use of multiple F options merges two output files and creates one output file with only from column 4 delimited by comma. However, the final output file is created with delimiter as PIPE due to use of option E.

In addition, the use of the Z option compresses the output files of pattern W_RTL_PLAN*.dat created at cloud:ri location into a compressed file as RI_MFP_DATA.zip and deletes the generated file after compressing.

Example 6: The following option shows the use of the M option to copy a set of files from one location to another location.

```
copy_dom_in|I|dom_in
copy_dom_in|O|ftp_out
copy_dom_in|M|*.dat|N
```

This example copies all files of the pattern *.dat from the application.input location to the Object Storage outgoing file area. Due to use of option N to not delete the input files, it only copies the file. To move the files, option Y should be used.

Example 7: To select columns from input file and place in output file along with specified header for output file.

```
xform_ex_header|F|xform_src1.csv
xform_ex_header|I|dom_in
xform_ex_header|O|dom_out
xform_ex_header|X|xform_dst2h.csv|1,3|first_header,second_header
```

In this example, the first and third columns of input file xform_src1.csv is placed into the output file xform_dst2h.csv, with the addition of the header line first_header,second_header as the first line of the output file. Note that this assumes that no header line was present in input file xform_src1.csv.

Custom Function: ap_set_datr

This feature allows product attributes to be assigned during item creation if the product attributes are defined as dimension (level) attributes. For this functionality, the product attribute hierarchy (for example, PATR) must be defined with two dimensions (levels) (product attribute value and product attribute). The mapping of the product attribute values to items must be defined in the measure at the item/product attribute intersection level (for example, addvprdattdtt). This custom function can be called in a customer's batch control framework to register the loaded product attributes as dimension (level) attributes.

This application-level function registers all the loaded product attributes as dimension (level) attributes that can take two parameters, product attribute measure and product attribute hierarchy name. It must be called each time a new set of product attributes is loaded.

The following example illustrates calling this custom function to register dimension (level) attributes. The product attribute measure name is addvprdattdtt and the product attribute hierarchy used by customer is patr. The ra_custom is the service name to be used to call the custom functions in batch_exec_list.txt and the custom function name is ap_set_datr. The two parameters for the function must be separated with ~.

Example:

```
batch_datr | ra_custom | ap_set_datr~addvprdattdtt~patr
```

Convert Informal Positions to Formal: formalize

The formalize service allows the modifying of current informal positions (which were created on a given hierarchy and dimension (level) having Dynamic Position Maintenance, or DPM, enabled) to make them formal positions. One or more files matching the pattern <hier>.formalize[.extension] must be uploaded via Object Storage to the planning/incoming/ input location. This file (or files) specifies which informal positions to formalize. An option is also available to allow the formalization of all current informal positions on a dimension (level). Parameters are specified via the batch_formalizepositions_list.txt batch control file.

The batch_formalizepositions_list.txt control file contains multiple lines to specify each formalize task, each with three required columns, as follows:

- Formalization Set Name.
- Parameter Type, from these values.

- C - Column index (starting from 1) of the dimension (level) position name in the hierarchy file (as generated by exportHier) [required].
- D - Dimension (level) to formalize [required].
- H - Hierarchy of the dimension (level) [required].
- A - Formalize all informal positions on Dim (no value needed) [optional; omit if sending a <hier>.formalize.dat file].
- Parameter Value (varies by parameter type).

If the (A)ll option is not provided, then at least one <hier>.formalize[.extension] file is expected to be available in Object Storage. If no formalize files are present, the batch task will report an error. File format details are available in the *Oracle Retail Predictive Application Server Cloud Edition Administration Guide*.

Here is an example specifying a formalization task called prod_sku, which operates on positions of the SKU dimension (level) in the PROD hierarchy:

```
prod_sku|H|prod|
prod_sku|D|sku|
prod_sku|C|1|
```

Rename Positions in a Hierarchy: renamepositions

The Rename Positions service enables the renaming of existing positions in a hierarchy. The task is configured by specifying the hierarchy on which positions are to be renamed and looks for a file with the name [hier].rn.dat in Object Storage. If the rename data file is not present, the rename task will exit without error so that the following batch sequence steps may continue.

The format of the rename data file is as specified in the *Oracle Retail Predictive Application Server Cloud Edition Administration Guide*.

The rename positions batch task does not require a separate control file, but may be specified as an entry in the batch_exec_list.txt file, for example:

```
weekly | renamepositions | prod
```

This control line indicates that the weekly batch task will look for a rename positions data file for the PROD hierarchy, prod.rn.dat, and will carry out the renamings specified.

Workspace Refresh by Template Name: refresh

The Workspace Refresh service enables the refresh of particular workspaces with current application data. This allows the selection of all workspaces built from a particular template, including the ability to match on partial template names.

The batch_refresh_list.txt contains only two columns: a refresh group identifier and a template name pattern to match. Here is an example of this file:

```
refresh_weekly | mt_wb
refresh_weekly | mp_wb
refresh_weekly | lt_wb
refresh_weekly | lp_wb
```

The example contains one refresh group, with four template pattern names to match. All workspaces that are built from templates matching those patterns will be refreshed.

Workspace Rebuild by Template Name: rebuild

The Workspace Rebuild service is similar to Workspace Refresh task; however, it allows for the workspaces to be completely rebuilt rather than just having their data refreshed. This covers the case where new positions have been added and must be reflected in the workspaces.

The `batch_rebuild_list.txt` contains only two columns: a rebuild group identifier and a template name pattern to match. Here is an example of this file:

```
rebuild_weekly | mt_wb  
rebuild_weekly | mp_wb
```

The example contains one rebuild group, with two template pattern names to match. All workspaces that are built from templates matching those patterns will be rebuilt.

Workspace Delete by Template Name: delete

The Workspace Delete service enables the bulk deletion of all workspaces built from a particular template. This service does not require a separate control file but can be fully specified within the `batch_exec_list.txt` file. All workspaces built from the given template will be removed. To remove workspaces from several template types, specify one delete task for each template.

Here is an example of an entry in the `batch_exec_list.txt` file for this task:

```
weekly | delete | AD_POC
```

By default, the associated segment will be removed in addition to the workspace. If the optional parameter `keepsegment` is used, workspaces will be deleted without deleting the segments.

Here is an example of an entry in the `batch_exec_list.txt` file for this task:

```
weekly | delete | AD_POC~keepsegment
```

Run Segment Build Queue: autobuild

The autobuild service is the simplest to configure in the RPASCE batch framework, as it requires no parameters to be specified. When the autobuild service is included in a batch task group, the `wbbatch` utility is run to invoke the `-startQueue` build option. Any segments that have been previously queued for automatic build will be created by this call. Since no further parameters are needed, there is no third column for the autobuild service line.

Here is an example of an entry in the `batch_exec_list.txt` file for this task:

```
batch_weekly | autobuild |
```

Note that nothing is required after the second pipe (|) character.

Sync Users From IDCS: idcssync

This task supports the same functionality as the existing OAT Task Synchronize Users from OCI IAM to be made part of a scheduled eebatch task. The task does not require any parameters and may be added to any batch such as:

```
batch_weekly | idcssync |
```

For further details about this task, see the section "Synchronize Users from OCI IAM" in the *Oracle Retail Predictive Application Server Cloud Service Administration Guide*.

Shared Build (optional)

It is possible to rebuild the workspaces in a shared manner using the shared keyword. Add the shared keyword after the template name separated by a ~ character. Use this option if the workspace rebuild step in the batch is taking a long time. It is especially useful for a dashboard rebuild, where the selections are usually the same across the users. The shared build uses a workbook copy instead of a workspace rebuild wherever possible. It considers the position security setup for the users and the selections used in the workspaces to decide whether a workspace copy can be done instead of a full rebuild. A workspace copy is much faster than a rebuild.

For example, security admin workbook was committed with product position security is as follows.

user1: 100

user2: 100

user3: 100

user4: 200

user5: 200

user6: 200

Location security is as follows.

user1: B&M

user2: B&M

user3: CA B&M

user4: B&M

user5: B&M

user6: B&M

Suppose all six users have only one workspace each of the template being rebuilt. User1, user2 and user3 have the matching selections for their workspaces. User4 and user5 have matching selections in the wizard, but user6 has a different positions selected.

Using the shared build, user1's workbook will be rebuilt. User 2 will get a copy of user1's workbook. User 3's workbook will also be rebuilt because user 3 has a different position security for location (compared to user1 and user2) even though position security is same for the product. User4 and user5 have matching product and location security so only user4's workbook will be rebuilt and user5 will get a copy of that workbook. Although user6 has same product and location security settings as user4 and user5, user6 made different selections for the workspace, so user6's workspace will also be rebuilt.

Example batch_rebuild_list.txt using the shared option.

rebuild_weekly | mt_wb

rebuild_weekly | mp_wb


rebuild_weekly | pl_db~shared

In this example, the workspaces for templates for mt_wb and mp_wb will be rebuilt in the traditional way, but the workspaces for template pl_db will use the shared mode of rebuild described above.

Configuration of interface.cfg

In RAP Integration, data from all pre-defined planning interfaces to external systems such as RMF CS or internal systems such as RI/Science must be pulled via importers from the RDX schema. Any data that is going from Planning to external systems can also be exported via exporters to the RDX schema. Although interface tables in the RDX schema are fixed or do not change very frequently, as defined by the interface contracts between respective applications, the planning/forecast application that is implemented on PDS supports extensibility and EE configuration. Because of this, it should have configurable/flexible importers and exporters to configure for all available metrics from the RDX schema tables since dimensions (levels)/fact names can be different for an EE customer. This is handled through the use of the interface.cfg file (interface configuration file). It is a free-form text file similar to the batch control file, and contains the mapping of dimension (level)/facts in PDS to columns mapped to external tables for each interface.

Figure 1-1 Interface.cfg



Both importers/exporters can be commonly referred as interfaces within PDS, with an unique interface ID for each interface. Interfaces are classified as follows: dimension (level) importers (H), data importers (I), and data exporters (E). [Table 1-2](#) shows the pre-defined list of

interfaces that are available for the customers in a RAP integration; there may be more application-specific interfaces. Customers can create or modify entries only for the available list of interfaces. They can configure the interface to match and import the required dimension (level)/fact data based on the dimension (level)/fact names configured within their application when those interfaces are executed in batch. For GA applications, a pre-configured interface.cfg file is available and the customer can customize it for any further extensibility changes, similar to an EE customer.

For most of the interfaces, the external interface table name is the same as the interface name; however, for few interfaces that require derived data from other interface tables, pre-defined views are created and columns from those views are used to obtain the data. Interfaces can be defined to only import/export to one external interface table/view. In [Table 1-3](#), the External View Name column is populated only for interfaces that use internal views. Source tables used to define the view are specified within brackets if it is different than the interface name. The incremental flag Y indicates that the interface is incremental in nature; that is, for each interface run it obtains only the changed data, compared to the previous run of the interface. However, if the incremental flag is N, the interface always obtains a full set of data for each run. All hierarchy interfaces are complete-extract interfaces in order to obtain the latest data available in other applications and so keep all integrating applications synchronized. Refer to the application-specific Implementation Guides for more details about the list of columns available and used for the import or export for each interface.

Table 1-2 List of Pre-Defined Interfaces

Interface Name	Interface Description	Importer Type	Interface Source/ Destination	External View Name	Incremental
RSE_FCST_DMD_EXP	Forecast Interface from Science	I	RSP		Y
W_PDS_SLS_IT_LC_WK_A	Sales Interface	I	RI		Y
W_PDS_INV_IT_LC_WK_A	Inventory Interface	I	RI		Y
W_PDS_MKDN_IT_LC_WK_A	Markdown Interface	I	RI		Y
W_PDS_PO_ONORD_IT_LC_WK_A	On Order Interface	I	RI		Y
W_PDS_INVRC_IT_LC_WK_A	Receipts Interface	I	RI		Y
W_PDS_INVADJ_IT_LC_WK_A	Inventory Adjustments	I	RI		Y
W_PDS_INVTSF_IT_LC_WK_A	Inventory Transfers	I	RI		Y
W_PDS_DEALINC_IT_LC_WK_A	Deal Incomes	I	RI		Y
W_PDS_SLSWF_IT_LC_WK_A	Wholesale/ Franchise	I	RI		Y
W_PDS_EXCH_RATE_D	Currency Conversion Rates	I	RI	VW_CURR_RATE	N
VW_LOC_DATA	Location Data	I	RI	VW_LOC_DATA	N

Table 1-2 (Cont.) List of Pre-Defined Interfaces

Interface Name	Interface Description	Importer Type	Interface Source/ Destination	External View Name	Incremental
W_PDS_PRODUCT_D	Product Hierarchy	H	RI		N
W_PDS_ORGANIZATION_D	Location Hierarchy	H	RI		N
W_PDS_CALENDAR_D	Calendar Hierarchy	H	RI	VW_CLND_HIER	N
VW_CURR_HIER	Currency Hierarchy	H		VW_CURR_HIER(W_PDS_EXCH_RATE_D)	N
MFP_PLAN1_EXP	Merch Plan Export from MFP to RI	E			N
MFP_PLAN2_EXP	Merch Target Plan Export from MFP to RI	E			N
MFP_PLAN3_EXP	Location Plan Export to from MFP to RI	E			N
MFP_PLAN4_EXP	Location Target Plan Export from MFP to RI	E			N

Interface Mappings

Each interface can have a configuration specification defined as the interface mapping that provides details about the mapping of the source table columns and the destination. It can be provided by the customer as the configuration file interface.cfg, which is loaded into an internal interface mapping table. It can be used by generic importer/exporter packages to transfer data when those interfaces are executed in the batch. [Table 1-3](#) provides a list of entries in the interface mapping table (RP_G_INTF_MAPPING_MD).

Table 1-3 Interface Mappings

Column	Description	Purpose	Example
INTF_MAP_NAME<INTERFACE_NAME>	Interface name	Actual interface name for which the mapping is defined	W_PDS_SLS_IT_LC_WK_A
INTF_MAP_PARAM<PARAM>	Interface parameter name	Grouping within that interface. Can be App Name or, within an application, a different set of data to process for that interface, based on this parameter.	MFP

Table 1-3 (Cont.) Interface Mappings

Column	Description	Purpose	Example
INTF_MAP_TYPE<TYPE>	Interface parameter type	Type of mapping. Can be dimension (level) mapping or data mapping or filter criteria for the mapping. Valid Interface Mapping types vary, based on the type of interface.	DIM01 / DATA
INTF_MAP_RPAS<INTERNAL_NAME>	Interface mapping column from PDS (RPASCE)	Dimension (level) or fact name from PDS, based on the mapping type.	WEEK / DRTYLSREGU
INTF_MAP_EXTERNAL<EXTERNAL_NAME>	Interface mapping column from external table (source or destination table)	Column name from external interface table.	NET_SALES_REG_UNITS
INTF_MAP_VALUE<VALUE>	Interface mapping value or constant	Can be a hard-coded constant value to use if mapping is not provided. It can be used for FILTER Type entries. It can also be a scalar measure specified with prefix @.	

Syntax for Interface Mappings

This section provides the syntax for interface mappings in the interface.cfg file.

```
<INTERFACE_NAME> : <PARAM> : <TYPE> : <INTERNAL_NAME> : <EXTERNAL_NAME> : <VALUE>
```

Here are the details for the entries.

<INTERFACE_NAME> - The name of interface

<PARAM> - Parameter grouping can be App Name or any internal grouping name. It must have a different value only if the same interface is used to import/export different levels of data, based on different criteria.

<TYPE> - For data importers/exporters, DIMxx (xx 01,02,03) for dimension mapping. DIM01 is reserved for the Calendar dimension. DATA for data mapping. FILTER for optional filter criteria. FILTER or FILTER_EQ used for equal (=) operator. It also allows FILTER_NE (<>), FILTER_GT (>), FILTER_GE (>=), FILTER_LT (<), FILTER_LE (<=)(<=), FILTER_LK (Like), FILTER_NL (Not Like) as different filter types. More than one filter entries can be used, but they all use the AND operation of the filter.

<TYPE> - For hierarchy/dimension importers, HDMxx (xx 01,02,03) for dimension (level) mapping for all dimensions (levels) from a single hierarchy, HDLxx for dimension (level) label mappings, FILTER* for optional filter criteria.

<INTERNAL_NAME> - For data importers/exporters, internal dimension (level)/fact name. It must be dimension (level) name for DIMxx type and fact name for DATA type entries.

<INTERNAL_NAME> - For hierarchy/dimension (level) importers, hierarchy dimension (level) column from a single hierarchy, it is required only for HDMxx type entries.

<EXTERNAL_NAME> - Mapping column from external interface table for dimension (level), data, or filter types.

<VALUE> - Constant value to use for mapping if column mapping not present. Also constant value to use for FILTER criteria. It can also be a scalar measure specified with prefix @. If this value is provided for hierarchy importer types, it will be used as the prefix for dimension (level) or labels

Multiple entries for same interface are required to completely define all the required mappings for an interface.

Example for Data Importer Interface

Entries for data importer interfaces are displayed as follows:

<INTERFACE_NAME> : <PARAM> : DIMxx : <DIM_NAME> : <EXTERNAL_COLUMN> :

<INTERFACE_NAME> : <PARAM> : DATA : <FACT_NAME> : <EXTERNAL_COLUMN> :

<INTERFACE_NAME> : <PARAM> : FILTER : <EXTERNAL_COLUMN> : <FILTER_VALUE>

Example:

W_PDS_SLS_IT_LC_WK_A: MFP: DIM01 : WEEK : EOW_DATE

W_PDS_SLS_IT_LC_WK_A: MFP: DIM02 : SKU : ITEM_ID

W_PDS_SLS_IT_LC_WK_A: MFP: DIM03 : STOR : LOCATION_ID

W_PDS_SLS_IT_LC_WK_A: MFP: DATA : DRTYNSLSREGU : NET_SALES_REG_UNITS

W_PDS_SLS_IT_LC_WK_A: MFP: DATA : DRTYNSLSREGC : NET_SALES_REG_COST

W_PDS_SLS_IT_LC_WK_A: MFP: DATA : DRTYNSLSREGR : NET_SALES_REG_RETAIL

W_PDS_SLS_IT_LC_WK_A: MFP: DATA : DRTYRTNREGU : RETURNS_REG_UNITS

W_PDS_SLS_IT_LC_WK_A: MFP: DATA : DRTYRTNREGC : RETURNS_REG_COST

W_PDS_SLS_IT_LC_WK_A: MFP: DATA : DRTYRTNREGR : RETURNS_REG_RETAIL

W_PDS_SLS_IT_LC_WK_A: MFP: DATA : DRTYNSLSCLRU : NET_SALES_CLEAR_UNITS

W_PDS_SLS_IT_LC_WK_A: MFP: DATA : DRTYNSLSCLRC : NET_SALES_CLEAR_COST

W_PDS_SLS_IT_LC_WK_A: MFP: DATA : DRTYNSLSCLRR : NET_SALES_CLEAR_RETAIL

W_PDS_SLS_IT_LC_WK_A: MFP: DATA : DRTYRTNCLRU : RETURNS_CLEAR_UNITS

W_PDS_SLS_IT_LC_WK_A: MFP: DATA : DRTYRTNCLRC : RETURNS_CLEAR_COST

W_PDS_SLS_IT_LC_WK_A: MFP: DATA : DRTYRTNCLRR : RETURNS_CLEAR_RETAIL

Example for Data Exporter Interface

Entries for data exporter interfaces are displayed as follows:<INTERFACE_NAME> :

<PARAM> : DIMxx : <DIM_NAME> : <EXTERNAL_COLUMN> :

<INTERFACE_NAME> : <PARAM> : DATA : <FACT_NAME> : <EXTERNAL_COLUMN> :

<INTERFACE_NAME> : <PARAM> : FILTER : <FACT_NAME> : :<FILTER_VALUE>

The following example shows a sample generic exporter that obtains data from different facts of same base intersection and imports data into same table for different versions (MPCP and MPOP) of the plan. This is controlled by using a different PARAM for each different version of the data.

MFP_PLAN1_EXP:MPOP:DIM01:WEEK:CLND_KEY:

MFP_PLAN1_EXP:MPOP:DIM02:SCLS:PROD_KEY:

MFP_PLAN1_EXP:MPOP:DIM03:CHNL:LOC_KEY:

MFP_PLAN1_EXP:MPOP:DATA::PROD_DH_ATTR:@MFP_DRDVDPOST

MFP_PLAN1_EXP:MPOP:DATA::SUPPLIER_NUM:@MFP_DRDVDPOST

MFP_PLAN1_EXP:MPOP:DATA::VERSION_NUM:0

MFP_PLAN1_EXP:MPOP:DATA:MPOPLDOWD:CAL_DATE:

MFP_PLAN1_EXP:MPOP:DATA:MPOPSLSU:SLS_QTY:

MFP_PLAN1_EXP:MPOP:DATA:MPOPSLSR:SLS_RTL_AMT:

MFP_PLAN1_EXP:MPOP:FILTER:MPOPEXPORTB::TMFP_PLAN1_EXP:MPCP:DIM01:WEEK:CLND_KEY:MFP_PLAN1_EXP:MPCP:DIM02:SCLS:PROD_KEY:MFP_PLAN1_EXP:MPCP:DIM03:CHNL:LOC_KEY:MFP_PLAN1_EXP:MPCP:DATA::PROD_DH_ATTR:@MFP_DRDVDPOSTMFP_PLAN1_EXP:MPCP:DATA::SUPPLIER_NUM:@MFP_DRDVDPOSTMFP_PLAN1_EXP:MPCP:DATA::VERSION_NUM:1MFP_PLAN1_EXP:MPCP:DATA:MPCPLDOWD:CAL_DATE:MFP_PLAN1_EXP:MPCP:DATA:MPCPSLSU:SLS_QTY:MFP_PLAN1_EXP:MPCP:DATA:MPCPSLSR:SLS_RTL_AMT:MFP_PLAN1_EXP:MPCP:FILTER:MPCPEXPORTB::T

Example for Hierarchy/Dimension (Level) Importer Interface

Hierarchy importers are similar to importers. However, the dimension (level) mapped belong to the same hierarchy. Each hierarchy dimension (level) can also contain the corresponding mapping for labels. The new mapping type entries differentiate an interface as a hierarchy importer interface.

Note

If the mapping is for an alternate level that is loaded via flat file and there is no mapping available in the External Interface table for the alternate level, then default value can be provided as NA or na. In this scenario, the current position name, if it already exists, is not overwritten. However, for a new value, the position name will be added as <level>_<number>, where <level> is the level name that is the alternate level here and <number> is an integer starting with 0. If the default value provided is not NA or na, then the position name will be saved as the default value provided.

The following two mappings are used instead of DIMxx and DATA type mappings.

<INTERFACE_NAME> : <PARAM> : HDMxx : <DIM_NAME> :

<EXTERNAL_DIM_COLUMN> : <OPTIONAL_PREFIX_VALUE>

<INTERFACE_NAME> : <PARAM> : HDLxx : : <EXTERNAL_LABEL_COLUMN> :

<OPTIONAL_PREFIX_VALUE>


```
<INTERFACE_NAME> : <PARAM> : FILTER : : <FILTER_SOURCE_COLUMN> :  
<FILTER_VALUE>
```

The following is an example entry for hierarchy importers.

```
W_PDS_CALENDAR_D:PDS:HDM01:DAY:DAY:  
W_PDS_CALENDAR_D:PDS:HDM02:WEEK:WEEK:  
W_PDS_CALENDAR_D:PDS:HDM03:MNTH:MNTH:  
W_PDS_CALENDAR_D:PDS:HDM04:QRTR:QRTR:  
W_PDS_CALENDAR_D:PDS:HDM05:HALF:HALF:  
W_PDS_CALENDAR_D:PDS:HDM06:YEAR:YEAR:  
W_PDS_CALENDAR_D:PDS:HDM07:WOYR:WOYR:  
W_PDS_CALENDAR_D:PDS:HDM08:HLDY::NA  
W_PDS_CALENDAR_D:PDS:HDM09:EVNT::NA  
W_PDS_CALENDAR_D:PDS:HDM10:STDB:STDB:  
W_PDS_CALENDAR_D:PDS:HDL01::DAY_LABEL:  
W_PDS_CALENDAR_D:PDS:HDL02::WEEK_LABEL:  
W_PDS_CALENDAR_D:PDS:HDL03::MNTH_LABEL:  
W_PDS_CALENDAR_D:PDS:HDL04::QRTR_LABEL:  
W_PDS_CALENDAR_D:PDS:HDL05::HALF_LABEL:  
W_PDS_CALENDAR_D:PDS:HDL06::YEAR_LABEL:  
W_PDS_CALENDAR_D:PDS:HDL07::WOYR_LABEL:  
W_PDS_CALENDAR_D:PDS:HDL08::Unassigned  
W_PDS_CALENDAR_D:PDS:HDL09::Unassigned  
W_PDS_CALENDAR_D:PDS:HDL10::STDB_LABEL:
```

Process for Uploading New interface.cfg File

The customer must upload the interface.cfg file to the object store using the naming convention `planning/incoming/config/interface.cfg` that will be used by the Application Deploy Task or the Patch Application Task.

The interface.cfg file is validated during the deploy or patch task, verifying that the correct parameters are used and the interface column mappings are valid both in the application and in the external table sources. If the validation fails, it will provide details about the errors in the log.

Application Deploy

This section describes the process for deploying an application in an RPASCE Cloud Service environment.

Object Storage Upload Location

Oracle RGPU cloud services include an Object Storage site for incoming and outgoing file transfers. See "[Uploading and Downloading Files](#)" for details on the Object Storage interface.

For the purposes of building the application, four paths within the Object Storage site are used:

config

For uploading the application configuration into the cloud environment, create a .zip archive containing the contents of the config directory (without the top level config folder). This archive file must be named as <config_name>config.zip. This archive file must be placed in the planning/incoming/config path on the Object Storage service. It may be updated as often as necessary in support of application build or patch activities.

Example

The ascs_config.zip may contain the following contents:

- ascs folder - this is the folder with configuration for an application called ASCS (required).
- ascsDashboardSettings.json - custom settings for the ASCS dashboard (optional).
- ascsHelpConfig.json - custom settings for ASCS Online Help (optional).

interface.cfg (optional)

See [Configuration of interface.cfg](#) and [Process for Uploading New interface.cfg File](#).

batch_control

The set of batch process control files, as detailed in the previous section, must be uploaded as planning/incoming/batch_control.zip (or alternatively as individual files in the planning/incoming/batch_control path) within the Object Storage service. These files are loaded into the application's data store during deployment and can be updated later as part of the Patch Application task..

Bootstrap Environment

A newly provisioned RPASCE cloud environment is set up with a bootstrap configuration that allows the implementer to log into the RPASCE Client and access the Online Administration Tool (OAT) interface before an application has been deployed. The bootstrap OAT configuration allows only tasks required to deploy your application. Once the application has been deployed, both the application-specific tasks and activities as well as the deploy activities will be available. This allows the application to be re-deployed from scratch multiple times, should this be required during the implementation phase. (Note that this would trigger a complete loss of any data, so would only be applicable in early phases of implementation testing.)

OAT Parameters

A few parameters must be specified when initiating an Application Deploy process through OAT. The implementer must supply these values:

Config Name

The name under which the configuration has been saved. For those familiar with the RPASCE application construction process, this is the name that is internally passed as the -cn parameter to rpaInstall. A drop-down list offers choices based on the available application config archive files in the incoming FTP area.

Partition Dim

The dimension (level) on which the application will be partitioned. The application is constructed with one sub-application for each position in the given dimension (level). This must be a level of separation that fits with the intended workflow for individual users so that, when possible, most users' daily tasks relate to only one sub-application. This lessens contention when many users are active in the system.

Batch Group

Once an application has been built successfully, a named group of batch operations may be specified (typically including measure data loads and mace calculations). This operation sequence must be one batch_type entry in the Batch Exec control file, batch_exec_list.txt (described in "[Batch Exec Service](#)").

Overwrite

In the case where the application has already been built once, and the implementer must rebuild the application from scratch, which might occur because a non-patchable change has been made to the configuration, this option must be selected. If it is left in the default unselected state, then the application build process will halt and report an error, rather than overwrite the existing application.

Application Build

The application build process automatically carries out the following steps:

1. Basic validation of the given config name and partition dimension (level).
2. Ensure that a configuration with the given config name has been uploaded.
3. If the overwrite flag is false, ensure that there is no existing application. It reports an error if the application exists.
4. If the overwrite flag is true, remove the existing application.
5. Build the application using the config name and the partition dimension (level) as specified in the OAT parameter screen.
6. Copy any users and user groups from the bootstrap application environment into the application environment.
7. Copy the uploaded batch control text files into the application from the SFTP location.
8. Run post-application-build batch group.
9. Add the application details into the provisioned RPASCE Client configuration.

Once the Bootstrap Application task has completed, you only need to log out of the RPASCE Client and then log back in again to see the tasks and menus associated with your newly built

application. (It is no longer required to restart the RPASCE Client, and this option has been removed from the OAT menus.)

File Transfer Service Required Parameters

To determine IDCS_SCOPE, refer to the tenant string portion (for example, rgbu-rap-cust-stg1-mfpSCS) of your cloud service URL (for example, <https://rap.retail.us-ashburn-1.ocs.oraclecloud.com/rgbu-rap-cust-stg1-mfpSCS/rpasceui/>).

Planning Cloud Service URL Pattern	Tenant	Scope
https://rap.retail.us-ashburn-1.ocs.oraclecloud.com/rgbu-rap-cust-stg1-mfpSCS/rpasceui/	rgbu-rap-cust-stg1-mfpSCS	rgbu:rpas:psraf-RPASCE-STG1
https://rap.retail.us-ashburn-1.ocs.oraclecloud.com/rgbu-rap-cust-stg1-apcs/rpasceui/	rgbu-rap-cust-stg1-apcs	rgbu:rpas:psraf-RPASCE-STG1
https://rap.retail.us-ashburn-1.ocs.oraclecloud.com/rgbu-rap-cust-stg1-ipocs/rpasceui/	rgbu-rap-cust-stg1-ipocs	rgbu:rpas:psraf-RPASCE-STG1
https://rap.retail.us-ashburn-1.ocs.oraclecloud.com/rgbu-rap-cust-stg1-rpasce/rpasceui/	rgbu-rap-cust-stg1-rpasce	rgbu:rpas:psraf-RPASCE-STG1

Based on the tenant string (for example, rgbu-rap-cust-stg1-mfpSCS), the environment index is stg1 and the application is mfpSCS. For this tenant string or for other applications such as apcs or ipocs tenant string, the IDCS scope will look like the configuration below (ensure environment index is in uppercase characters only):

IDCS_SCOPE = rgbu:rpas:psraf-RPASCE-STG1

Create the OAuth Client in Retail Home with the following parameters:

- App Name: APP_STG1
- Description: FTS for STG1
- Scope 1: rgbu:rpas:psraf-RPASCE-STG1

This generates an OAuth Client with details like this:

- Oauth client:
- App Name: APP_STG1
- Client Id: APP_STG1_APPID
- Client Secret: 6aae7818-309b-4e7a-874e-f26356a675b1

You must capture Client Id and Client Secret. So set the FTS script variables as follows:

Copy

BASE_URL="https://rap.retail.eu-frankfurt-1.ocs.oraclecloud.com"

TENANT="rgbu-rap-cust-stg1-rpasce"

IDCS_URL="https://oci—iam-

a4cbf187f29d4f41bc03fffb657d5513.identity.oraclecloud.com/oauth2/v1/token"

IDCS_CLIENTID="APP_STG1_APPID"

IDCS_CLIENTSECRET="6aae7818-309b-4e7a-874e-f26356a675b1"

IDCS_SCOPE="rgbu:rpas:psraf-RPASCE-STG1"

2

In-Context Help

This chapter describes how to configure In-Context Help for solutions based on RPASCE.

In-Context Help is a resource to access relevant help topics, in the format of HTML and video, within the application. At present, it focuses on help topics related to the dashboard and the workspace. The naming convention is <app-name>HelpConfig.json.

Navigating to Help Topics on RPASCE

You can navigate to the help topics in the following ways:


Dashboard

The help topics for the dashboard are added to the following two levels:

- All: The generic topics related to MFP or A&IP are added to this level.
- Report: This consists of topics related to dashboards such as the effective usage, how to analyze the metrics, and so on.


[Figure 2-1](#) shows the view of a dashboard.

Figure 2-1 Dashboard Window



The help topics for the dashboard are visible on the right side panel, as shown in [Figure 2-2](#).

Figure 2-2 Dashboard Help Topics




Workspace


The workspace contains the actual content related to MFP or A&IP. Here the topics are aligned with respect to the different levels of the Taskflow.

[Figure 2-3](#) illustrates the workspace for the product MFPRCS.

Figure 2-3 MFPRCS Workspace



Here the Step, Tabs, and View are visible.

Figure 2-4 MFPRCS Workspace with Help

Creating the Contextual Help Configuration File

The specifications related to Contextual Help for the RPASCE dashboard and workspace are implemented by creating a configuration file. This file is created outside of the RPASCE Configuration Tools and is deployed in the RPASCE Client application. The contents of this configuration file are used by the RPASCE Client to determine how to organize and display the help topics in the dashboard and the workspace.

Although a Contextual help configuration file can be created from scratch, in most cases, it is simpler to modify an existing version of the file to incorporate any desired changes.

Using JSON in the Contextual Help Configuration File

The contents of the Contextual Help Configuration file are formatted as a JSON (JavaScript Object Notation) object. JSON is a common flexible information encoding notation used frequently in cloud applications; it is more compact and, when properly formatted, more readable than the XML format. (Importantly, it is also not subject to some security concerns that are present when using XML for information encoding.)

JSON is a simple and straightforward format; information about the specifics of the format is readily available online.

Structure of Contextual Help Configuration File

The configuration file is divided into three levels: ALL, REPORTS, and WORKBOOKS. All three levels are of type JSON Object. The ALL level is the generic level. REPORTS and WORKBOOKS are children of level ALL.

Table 2-1 Configuration File Levels

Level	Description
ALL	Describes the generic help topics related to the RPASCE solution in use.
REPORTS	Contains the help topics related to the dashboard.
WORKBOOKS	Contains the help topics for the workbook and its sub-categories, such as Task, Step, Tab, and View.

The generic JSON structure for any solution is as follows:

```
"helpTopics" : [] "reports" : { "helpTopics" : [] } "workbooks" : { "helpTopics" : [] }
```

Help Topic Building Block

The help topics object as a whole is a JSON array of collection of attributes. This help topics object is the building block for all the different levels.

The following JSON snippet explains the generic helpTopics object structure:

```
"helpTopics" : [{  
  "name" : "Help Topic 1",  
  "description" : "Description 1",  
  "url" : "URL 1",  
  "type" : "Type 1",  
  "imageSrc" : "Image 1",  
  "color" : "Color 1"  
},{  
  "name" : "Help Topic 2",  
  "description" : "Description 2",  
  "url" : "URL 2",  
  "type" : "Type 2",  
  "imageSrc" : "Image 2",  
  "color" : "Color 2"  
}]
```

[Table 2-2](#) list the help topic properties.

Table 2-2 Help Topic Properties

Property	Value Type	Description
Name	JSON String	The name of the topic.
Description	JSON String	A short description of the topic.
URL	JSON String	The URL link to the help topic.
Type	JSON String	The type of the resource. Values are: document, image, or video.
ImageSrc	JSON String	The path to the image file to be displayed in the Help topic card, for example, an icon representing a video or an illustrative screenshot.

Table 2-2 (Cont.) Help Topic Properties

Property	Value Type	Description
Color	JSON String	The color in which the help topic tile should be visible. Color is displayed at the top of the Help topic card. It is typically used to visually distinguish between help formats (document or video), but may be used for a variety of purposes. Values are: lightblue, red, lightgreen, purple, blue, grey, orange, turquoise, green.

Key Naming Convention

The naming convention of the key depends upon the level or sub-level of each element. Here is an example of the naming conventions at different levels.

Consider the solution in use is mfprcs.

Table 2-3 MFPRCS Key Naming Example

Level/Sub-Level	Key Example	Description
All	NA	No need of the key as help topics are added to the root of the JSON.
Reports	reports	
Reports > Dashboard	reports.dashboard.id	The key must match the name provided for reports in the Taskflow_MultiSolution.xml file.
Workbooks	workbooks	
Activity > Task	mfprcs.Activity1.Task1	The task name must match the entry provided in Taskflow_MultiSolution.xml file for the specific task.
Activity > Task > Step	mfprcs.Activity1.Task1.Step1	The step name must match the entry provided in Taskflow_MultiSolution.xml file for the specific step.
Activity > Task > Step > Tab	mfprcs.Activity1.Task1.Step1.Tab1	The tab name must match the entry provided in Taskflow_MultiSolution.xml file for the specific tab.
Activity > Task > Step > Tab > View	MT_TB01_WS01	The view name must match the entry provided in Taskflow_MultiSolution.xml file for the specific view. The view key name is unique, as it can be added anywhere under Task, Step, or Tab from the solution.

JSON Structure of Contextual Help Configuration File

Here is an example of JSON object containing all the three levels and the help topics related to each of them. The `maxTopics` in the following snippet defines how many topics can be visible on RPASCE. This value must be increased if you want to show more help topics at a given level than the value of `maxTopics`. If, for a specific level, there are fewer than `maxTopics` topics, it fetches the remaining topics from its parent. In the following snippet the `maxTopics` for workbooks is set to 2 and overrides the `maxTopics` for the root, which is set to 3 for the workbooks level. Also, since no `maxTopics` is set for reports, the maximum topics for this level is capped to 3, which is fetched from the root level.

```
{
  "maxTopics": "3.0",
  "helpTopics": [ {
    "name": "MFP Cloud Service Introduction",
    "description": "Learn the steps for defining the strategic financial targets and creating plans that reconcile to the stated targets.",
    "url": "http://docs.oracle.com/cd/E75764_01/merchfinplan/pdf/cloud/161/html/retail_implementer_guide/output/introduction.htm#introduction",
    "type": "document",
    "imageSrc": "",
    "color": "turquoise"
  } ],
  "reports": {
    "helpTopics": [ ],
    "reports.dashboards.id": {
      "helpTopics": [ {
        "name": "Using the dashboard",
        "description": "Manipulate the dashboard in order to effectively analyze plan matrices",
        "url": "http://docs.oracle.com/cd/E75764_01/merchfinplan/pdf/cloud/161/html/retail_implementer_guide/output/dashboard.htm#dashboard",
        "type": "document",
        "imageSrc": "",
        "color": "turquoise"
      } ]
    }
  },
  "workbooks": {
    "maxTopics": "2.0",
    "helpTopics": [ ],
    "mfprcs.Activity1.Task1": {
      "helpTopics": [ {
        "name": "Overview of Merch Plan Targets",
        "description": "Learn about the steps associated with creating and monitoring targets",
        "url": "http://docs.oracle.com/cd/E75764_01/merchfinplan/pdf/cloud/161/html/retail_implementer_guide/output/CreateMerchPlanTargets.htm#create_merch_plan_targets_task",
        "type": "document",
        "imageSrc": "",
        "color": "turquoise"
      } ]
    }
  }
}
```

Editing the Contextual Help Configuration File

Help topics can be edited or added directly under the levels ALL and REPORTS. For level WORKBOOKS, the implementer can add or edit under Task or can add or edit under a specific sub-level (Step, Tab, or View).

The following examples indicate where the implementer can add help topics at different levels.

- Adding or editing the help topic for level ALL.

The implementer can add the help topic object directly under the root of the JSON under the property helpTopics. For editing, the implementer must search the name of the help topic in JSON and edit any of the required properties.

- Adding or editing the help topic for level REPORTS.

Here the implementer must add the help topic under the reports object of the JSON. The implementer must search for the key reports and then add the help topic under the attribute helpTopics. Similarly, any particular help topic can be edited by searching the name of the help topic.

- Adding or editing the help topic for sub-level Step under level WORKBOOKS.

To add a topic under sub-level Step, the implementer must search for the Step key and add the help topic. For editing, the implementer must search for a particular help topic and edit any of the properties as required.

- Adding or editing the help topic for sub-level View under level WORKBOOKS.


To add a topic under sub-level View, the implementer must search for the View key and add the help topic. For editing, the implementer must search for a particular help topic and edit any of the properties as required.

Retrieve/Update InContext help JSON file:

The user can update or retrieve the help JSON file through an OAT (Online Admin Tools) task and can easily update the existing JSON file or retrieve it. This provides the flexibility to view the list of available help resources and modify them according to the requirement.

Following are the steps to submit the OAT task.

1. Open **Submit a New Admin Task** under Online Admin Tools.
2. Select **Patch Application Task** under task group and click **Next**, as shown in [Figure 2-5](#).

Figure 2-5 List of Task Groups


Submit a New Admin Task

Select Task Group

- ☐ Configured Batch Tasks
- ☐ PDS Admin Tasks
- ☐ System Admin Tasks
- ☐ SR Admin Tasks
- ☐ Bootstrap Tasks
- ☒ Patch Application Task

Cancel Next > Finish

3. Select **Manage JSON files** from the list of available tasks and click **Next**, as shown in [Figure 2-6](#).

Figure 2-6 List of Tasks Under Patch Application Task Group

Submit a New Admin Task

Select A Task From Patch Application Task Group

Patch Application
Retrieve Batch Control Files
Upload Batch Control Files
Manage JSON files
Download Application Config

Cancel < Previous Next > Finish

4. Now the user can provide a task label and select the type of operation to be performed.
 - **Retrieve JSON files to Object Storage:** This operation performs the task of fetching the help JSON file from the RPASCE application. When this task is run, the help JSON file (with other JSON files) is bundled as a zip with label as <app_name>_json.zip and is placed in object storage under <SubNamespace>/planning/outgoing. The help JSON file is also prefixed with the app name as <app_name>HelpConfig.json

Example: mfprcsHelpConfig.json

Refer to [Uploading and Downloading Files](#) for more details about downloading and uploading files to Object Storage.

- **Update JSON files from Object Storage:** The user can update the help JSON file as per their requirements. Once updated, the file name must be prefixed with the app name as <app_name>HelpConfig.json. Then, this JSON file must be bundled as <app_name>_json.zip and placed in the <SubNamespace>/planning/incoming/config directory.

When the Update JSON files from Object Storage operation is performed on the RPASCE UI, it fetches the zip bundle from the Object Storage location <SubNamespace>/planning/incoming/config and updates the application with the new changes from the help JSON file. The user must re-login to the application to see the changes.

Refer to [Uploading and Downloading Files](#) for more details about downloading and uploading files to Object Storage.

Figure 2-7 Options to Fetch or Update the JSON Files

Submit a New Admin Task

Specify the arguments for task:

Task Label

Manage JSON Files

Operations

☒ Retrieve JSON files to Object store

☐ Update JSON files from Object store

Cancel < Previous Next > Finish

Note

If the user updates the URLs for the help topics in the help JSON file, these URLs must be allowed so that the links are accessible from the RPASCE UI. To allow the URLs, the user must navigate to System Configuration > Config Properties > Images and append the URL host in **Valid Image URL Hosts** text box.

Figure 2-8 Location to Allow List of the URLs

The screenshot displays the 'System Configuration' interface with the 'Images' tab selected. On the left, a sidebar lists 'Config Properties' (selected), 'Logging', 'Format', and 'Pivot Table'. The main content area shows the following settings:

- Disable Image File Type Validation:** A toggle switch that is currently turned off.
- Valid Image Type:** A text input field containing the value 'jpg,jpeg,png,gif'.
- Valid Image URL Hosts:** A text input field containing the value 'docs.oracle.com,www.youtube.com,'.

3

Uploading and Downloading Files

The Oracle Cloud Infrastructure Object Storage service is used to upload and download the files used in batch processing.

Object Storage

The Oracle Cloud Infrastructure Object Storage service is an internet-scale, high-performance storage platform that offers reliable and cost-efficient data durability. The Object Storage service can store an unlimited amount of unstructured data of any content type.

More information on Object Storage can be found here.

<https://docs.oracle.com/en-us/iaas/Content/Object/Concepts/objectstorageoverview.htm>

Accessing Endpoints to Manage Files in Object Storage

A Public Wrapper API over the Object Storage that has a built-in virus scanning ability is been available to perform various actions on Object Storage.

The following terms are used in [Table 3-1](#):

- **PAR:** a pre-authenticated request used to upload or download files. This is valid only for a limited duration and is set to five minutes.
- **Storage Prefix:** Object Storage is a flat storage area and does not include the concept of directories. Storage prefix is a prefix for a file that imitates a directory structure.

For example, planning/incoming is prefixed to a filename to provide a more readable and distinguishable name.

Before accessing the APIs, an OCI IAM token must be generated. This token is passed in the request header for authentication.

```
curl -i -u "<IDCS-client-id>:<IDCS-client-secret>" \
https://<idcs-tenant-id>.<IDCS_URL> \
-H 'Content-Type: application/x-www-form-urlencoded' \
-H 'Host: <idcs-tenant-id>.<IDCS_URL>' \
-d 'grant_type=client_credentials' -d 'scope=urn:opc:idm:__myscopes__'
```


Table 3-1 API Endpoints

Action	Endpoint	Payload	Response	Details
Get PAR (pre-authenticated requests) for upload of files	/uploadFiles	[{ "storagePrefix": "string", "fileName": "string" }, ...]	PAR URI	This endpoint is used to generate PARs, which are then used to upload files. Data: <pre>{ "listOfFiles": [{ "storagePrefix": "<subnamespace>/planning/incoming/input", "fileName": "prod.csv.dat" }, { "storagePrefix": "<subnamespace>/planning/incoming/config", "fileName": "RetailHomeConfig.json" } }]</pre> Command: <pre>curl -X POST "<url>/<BucketName>/uploadFiles" \ -H "accept: application/json" -H "Accept-Language: en" -H "Authorization: Bearer <AccessToken>" -H "Content-Type: application/json" \ -d '{"listOfFiles": [{"storagePrefix": "<subnamespace>/planning/incoming/input", "fileName": "prod.csv.dat"}, {"storagePrefix": "<subnamespace>/planning/incoming/config", "fileName": "RetailHomeConfig.json"}]}'</pre>

Table 3-1 (Cont.) API Endpoints

Action	Endpoint	Payload	Response Details
			Response 200: <pre>{ "parList": [{ "id": "WhmJ1Jn6v1GufaHDVISg2sUyiOLEoDAG3rW GUp1J/ yj7NgvpJtf77q6Qehsz9h9R:<subnamespace>/ planning/incoming/input/prod.csv.dat", "name": "prod.csv.dat", "accessUri": "https://objectstorage.us- phoenix-1.oraclecloud.com/p/ oKDbdsdO0T3LsfEWgys5WMD85DOyB7W4Av NK_IYXGtVMkGobebU6NIdvuz5AqrtO4/n/ oraclegbudevcorp/b/<BucketName>/o/ <subnamespace>/planning/incoming/input/ prod.csv.dat", "objectName": "<subnamespace>/planning/ incoming/input/prod.csv.dat", "accessType": "ObjectWrite", "timeExpires": 1629914865691, "timeCreated": 1629914565988 }, { "id": "I0zDNVNqpQG8KEgGoJokViRIZ6yAQNX7ha WIVBfDME+UabAShOhVu7zNvmERkZLm:<sub namespace>/planning/incoming/config/ RetailHomeConfig.json", "name": "RetailHomeConfig.json", "accessUri": "https://objectstorage.us- phoenix-1.oraclecloud.com/p/ Oja49u66xQqkzgOC6i5GA1PooED1XQV2bsnD wurqKbwetAnqX1RzVb4-e1mPiWWs/n/ oraclegbudevcorp/b/<BucketName>/o/ <subnamespace>/planning/incoming/config/ RetailHomeConfig.json", "objectName": "<subnamespace>/planning/ incoming/config/RetailHomeConfig.json", "accessType": "ObjectWrite", "timeExpires": 1629914866213, "timeCreated": 1629914566301 }] }</pre> Files can then be uploaded using the generated PARS (accessURI in the response). <pre>curl --request PUT --data-binary <File> <PAR></pre>

Table 3-1 (Cont.) API Endpoints

Action	Endpoint	Payload	Response	Details
Get PAR for download of files	/downloadFiles	[{ "storagePrefix": "string", "fileName": "string" }, ...]	PAR URI	This endpoint is used to generate PARs, which are then used to download files. Data: <pre>{ "listOfFiles": [{ "storagePrefix": "<subnamespace>/planning/incoming/input", "fileName": "prod.csv.dat" }, { "storagePrefix": "<subnamespace>/planning/incoming/config/", "fileName": "RetailHomeConfig.json" }] }</pre> Command: <pre>curl -X POST "<url>/<BucketName>/downloadFiles" \ -H "accept: application/json" -H "Accept-Language: en" -H "Authorization: Bearer <AccessToken>" -H "Content-Type: application/json" \ -d '{"listOfFiles": [{"storagePrefix": "<subnamespace>/planning/incoming/input", "fileName": "prod.csv.dat"}, {"storagePrefix": "<subnamespace>/planning/incoming/config/", "fileName": "RetailHomeConfig.json"}]}'</pre>

Table 3-1 (Cont.) API Endpoints

Action	Endpoint	Payload	Response Details
			Response 200: <pre>{ "parList": [{ "id": "SMINYf9O09IQmfkIxb8gHb0oRN2VrgAD88kn bvo3pcNvvrNEhG8btWlPOdnfcLRG:<subnames pace>/planning/incoming/input/prod.csv.dat", "name": "prod.csv.dat", "accessUri": "https://objectstorage.us- phoenix-1.oraclecloud.com/p/ M7JSr6Jp4up_XnVgib6xXqCuc17YHoWZDVzw Gmt1x76_sqIRTQGHS3X_5aMar2HV/n/ oraclegbudevcorp/b/<BucketName>/o/ <subnamespace>/planning/incoming/input/ prod.csv.dat", "objectName": "<subnamespace>/planning/ incoming/input/prod.csv.dat", "accessType": "ObjectRead", "timeExpires": 1629916720360, "timeCreated": 1629916420483 }, { "id": "8Jtqp6T2g3k+1KY9RhO9D7Kftmm5OBn6PlhC zxIQA9H9jbvyQmi54SNoXuEzx0eqM:<subnames pace>/planning/incoming/config/ RetailHomeConfig.json", "name": "RetailHomeConfig.json", "accessUri": "https://objectstorage.us- phoenix-1.oraclecloud.com/p/ 5wvRsj2D00nRkjX7- IMZoo9xOSRkMJUM37yyy4wKL1PKwTpdgQ8 BWQKlg_jHXnrh/n/oraclegbudevcorp/b/ <BucketName>/o/<subnamespace>/planning/ incoming/config/RetailHomeConfig.json", "objectName": "<subnamespace>/planning/ incoming/config/RetailHomeConfig.json", "accessType": "ObjectRead", "timeExpires": 1629916720632, "timeCreated": 1629916420742 }] }</pre> Files can then be downloaded using the generated PARs (accessURI in the response). <pre>curl --request GET <PAR> --output <file></pre>

Table 3-1 (Cont.) API Endpoints

Action	Endpoint	Payload	Response	Details
Delete Files	/deleteFiles	<pre>[{ "storagePrefix": "string", "fileName": "string" }, ...]</pre>	Status: ok/ error per file	This endpoint is used to delete files from Object Storage. Data: <pre>{ "listOfFiles": [{ "storagePrefix": "<subnamespace>/planning/ incoming/input", "fileName": "prod.csv.dat" }, { "storagePrefix": "<subnamespace>/planning/ incoming/config/", "fileName": "RetailHomeConfig.json" }] }</pre> Command: <pre>curl -X DELETE "<url>/<BucketName>/ deleteFiles" \ -H "accept: */*" -H "Accept-Language: en" -H "Authorization: Bearer <AccessToken>" -H "Content-Type: application/json" \ -d "{ \"listOfFiles\": [{ \"storagePrefix\": \"<subnamespace>/planning/ incoming/input\", \"fileName\": \"prod.csv.dat\" }, { \"storagePrefix\": \"<subnamespace>/planning/ incoming/config/ \", \"fileName\": \"RetailHomeConfig.json\" }] }"</pre> Response 200: <pre>{ "filesDeleted": [{ "filePath": { "storagePrefix": "<subnamespace>/ planning/incoming/input", "fileName": "prod.csv.dat" }, "responseMessage": "File successfully deleted <subnamespace>/planning/incoming/ input/prod.csv.dat" }, { "filePath": { "storagePrefix": "<subnamespace>/ planning/incoming/config/", "fileName": "RetailHomeConfig.json" }, "responseMessage": "File successfully deleted <subnamespace>/planning/incoming/ config/RetailHomeConfig.json" }], "filesFailedDeletion": [] }</pre>

Table 3-1 (Cont.) API Endpoints

Action	Endpoint	Payload	Response	Details
Move/ Rename Files	/moveFiles	[{ currentPath: { "storagePrefix": "string", "fileName": "string" }, newPath: { "storagePrefix": "string", "fileName": "string" } }, ...]	Status: ok/ error per file	This endpoint is used to move files within Object Storage. Data: <pre>{ "listOfFiles": [{ "currentPath": { "storagePrefix": "<subnamespace>/ planning/incoming/input2", "fileName": "prod.csv.dat" }, "newPath": { "storagePrefix": "<subnamespace>/ planning/incoming/config1/", "fileName": "prod.csv.dat" } }] }</pre> Command: <pre>curl -X POST "<url>/<BucketName>/movefiles" \ -H "accept: */*" -H "Accept-Language: en" -H "Authorization: Bearer <AccessToken>" -H "Content-Type: application/json" \ -d "{ \"listOfFiles\": [{ \"currentPath\": { \"storagePrefix\": \"<subnamespace>/planning/ incoming/ input2\", \"fileName\": \"prod.csv.dat\" }, \"newPath\": { \"storagePrefix\": \"<subnamespace>/planning/ incoming/ config1/\", \"fileName\": \"prod.csv.dat\" } }] }"</pre> Response: <pre>{ "failedMove": [], "successfulMove": [{ "moveFile": { "currentPath": { "storagePrefix": "<subnamespace>/ planning/incoming/input2", "fileName": "prod.csv.dat" }, "newPath": { "storagePrefix": "<subnamespace>/ planning/incoming/config1/", "fileName": "prod.csv.dat" } }, "responseMessage": "Successfully moved." }] }</pre>

Table 3-1 (Cont.) API Endpoints

Action	Endpoint	Payload	Response	Details
List storage prefixes	/listStoragePrefixes	<pre>{ "storagePrefix": "string", "fileNameStartsWith": "optional_string" }</pre>	Storage prefix name, Size, Number of files	This endpoint is used to list Storage Prefixes in Object Storage. Allows customer to discover consumption and storage prefix names. <pre>curl -X GET "<url>/<BucketName>/listprefixes" -H "accept: application/json" -H "Accept-Language: en" -H "Authorization: Bearer <AccessToken>"</pre> Response: 200 <pre>["<subnamespace>/planning/incoming/config", "<subnamespace>/planning/incoming/input"]</pre>
List files within a storage prefix	/listFiles	<pre>{ "storagePrefix": "optional_string" }</pre>	storage prefix name, file name, size, md5 checksum, created date, modified date, scan date, scan status	This endpoint is used to find and list files from Object Storage. <pre>curl -X GET "<url>/<BucketName>/listfiles?prefix=<subnamespace>/planning/incoming&contains=prod&sort=size:asc" \-H "accept: application/json" -H "Accept-Language: en" -H "Authorization: Bearer <AccessToken>"</pre> Response: <pre>{ "resultSet": [{ "name": "<subnamespace>/planning/incoming/config1/prod.csv.dat", "size": 177023, "md5": "v1N/r8gbNyQ1EdsC++Hv1w==", "version": "ca60582d-bacb-4309-bbbf-89d4a1aa2843", "etag": "7d6dde3b-5b5b-430d-8494-78e090418946", "createdDate": "2021-08-25T20:36:40Z", "modifiedDate": "2021-08-25T20:36:40Z", "scanStatus": "Passed" }], "totalResults": 1, "limit": 0, "count": 1, "offset": 0, "hasMore": false }</pre>

Table 3-1 (Cont.) API Endpoints

Action	Endpoint	Payload	Response	Details
Find file	/findFileByName	{ "stringContains": "string" }	storage prefix name, file name, size, md5 checksum, created date, modified date, scan date, scan status	This endpoint is used to find and list files from Object Storage. <pre>curl -X GET "<url>/<BucketName>/findFileByName?prefix=<subnamespace>/planning/incoming&contains=prod&sort=size:asc" \ -H "accept: application/json" -H "Accept-Language: en" -H "Authorization: Bearer <AccessToken>"</pre> Response: <pre>{ "resultSet": [{ "name": "<subnamespace>/planning/incoming/config1/prod.csv.dat", "size": 177023, "md5": "v1N/r8gbNyQ1EdsC++Hv1w==", "version": "ca60582d-bacb-4309-bbbf-89d4a1aa2843", "etag": "7d6dde3b-5b5b-430d-8494-78e090418946", "createdDate": "2021-08-25T20:36:40Z", "modifiedDate": "2021-08-25T20:36:40Z", "scanStatus": "Passed" }], "totalResults": 1, "limit": 0, "count": 1, "offset": 0, "hasMore": false }</pre>
Liveness test	/ping			This endpoint allows customer to check for service liveness. <pre>curl -X GET "<url>/ping" -H "accept: */*" -H "Accept-Language: en" -H "Authorization: Bearer <AccessToken>"</pre> Response: <pre>{ "appStatus": 200 }</pre>

A

Appendix: Exit Codes

This appendix describes all non-success exit codes from the Batch Framework services and batch administration tasks.

All EE batch scripts have consistent exit codes. Codes from 1 to 22 come from the BSA framework (although only 6 and 13 are commonly used by EE batch and so are included in the table below). Codes of 30 and above are from EE batch scripts themselves and are also listed in [Table A-1](#).

[Table A-1](#) lists the common (non-success) exit codes from the EE batch scripts and the BSA framework.

Table A-1 Common Exit Codes

Code	Reason
6	too few args / missing arg
13	invalid application path
30	required environment variable is not set
31	batch config file is not found
32	selected batch config entry is not found in file
33	invalid or missing info in batch config file
34	unknown error detected in RPASCE utility log output
35	file/directory not found when moving or copying files
36	file/directory permission error when moving or copying files
37	measure load exceeded reject record limit.

Note that in a live OCI-provisioned environment, it is not expected that customers will see any of these error codes except 31 through 33. These codes indicate issues in the customer-provided batch config files.

[Table A-2](#) lists additional exit codes from `eebatch_exporthier.ksh`, `eebatch_exportmeas.ksh`, `eebatch_loadhier.ksh`, and `eebatch_loadmeas.ksh`, that result from the exit codes of the underlying RPASCE binary utilities (`exportHier`, `exportMeasure`, `loadHier` and `loadMeasure`). The exit codes from the binary utilities are reported by the EE Batch Framework as being 100 more than the raw utility results. This prevents overlap between the BSA/EE script result codes and the RPASCE binary utility result codes. If `loadHier` itself returns an error code of 5, then the EE batch framework will report the error as code 105.

Table A-2 Additional Exit Codes

Script	Code	Reason
Generic codes applied to all scripts	103	Invalid application. Version mismatch.
	104	Generic argument error of the underlying utility.
	105	Generic exception occurred during main operation.

Table A-2 (Cont.) Additional Exit Codes

Script	Code	Reason
	106	Lock exception or parallel sub-process error.
eebatch_calc.ksh	107	Expression parsing error.
eebatch_exportmeas.ksh	108	Error during export preparation.
	109	Error during main execution.
	110	Error during post operation. Possible during the merging of local application files.
eebatch_loadhier.ksh	108	loadHier cannot add a new position to a partition dimension (level). For example, no store has been defined for the new position.
	109	Calendar prepending error.
	110	Input data contains conflicting information.
	111	Metadata error. Corrupted internal data.
	112	Unable to update the ITT table for the hierarchy that is shared by PDS.
	113	Data mover staging error.
	114	Data mover merging error. Hierarchy update was applied but measure data was not moved completely. The user must fix the underlying issue and re-run the operation to complete the hierarchy update.
	115	NA handler error. Hierarchy update was applied but measure data was not moved completely. The user must fix the underlying issue and re-run the operation to complete the hierarchy update.
	116	Purge all failed.
	117	Reindex is in progress. No operation was performed.
	120	PDS repartitioning is in progress.
eebatch_loadmeas.ksh	98	Internal aggregation error
	99	Internal aggregation error. Cannot load in CLR mode because the measure does not have a clear intersection. Unknown internal error.

It is not expected that customers will encounter any of the RPASCE exceptions, internal errors, or C++ exceptions, which indicate corrupted data or a programming error.