CBU Reference Guide

V4.2
Document ID: TMGN-05-4.2-01
Date Published: 3.5.04

© 1997–2004 edocs® Inc. All rights reserved.

edocs, Inc., One Apple Hill Dr., Natick, MA 01760

The information contained in this document is the confidential and proprietary information of edocs, Inc. and is subject to change without notice.

This material is protected by U.S. and international copyright laws. edocs and eaPost are registered in the U.S. Patent and Trademark Office.

No part of this publication may be reproduced or transmitted in any form or by any means without the prior written permission of edocs, Inc.

eaSuite, eaDirect, eaPay, eaCare, eaAssist, eaMarket, and eaXchange are trademarks of edocs, Inc.

All other trademark, company, and product names used herein are trademarks of their respective companies.

Printed in the USA.

Preface

In This Section

Using this Manual..... iv
Finding the Information You Need ix
If You Need Help..... xiii

Using this Manual

Welcome to the Communications Billing and Usage (CBU) Reference Guide.

This manual is a reference guide to the CBU and its components.

Before You Get Started

You should be familiar with the following:

- Your application architecture
- The CBU
- Designing or working with databases and data warehouses
- SQL

Who Should Read this Manual

This manual is a reference guide for the CBU. This guide is for anybody who needs information about content and structure of the CBU.

The CBU Reference Guide deals with the conceptual model of the CBU and its submodels. For more detailed information about the CBU, refer to the CBU *Reference* documentation corresponding to your database platform.

- Administrators

  You will find information about the conceptual structure of the CBU. There is also some information about customizing that is important when working with solutions with customizations. There is also important information about loading the CBU.

- Developers

  This guide contains the conceptual structure of the CBU you can use to understand how the CBU organizes information. You need to be familiar with the tables and their relationships. There is also important information about loading the CBU.

- Project Architect

  The most useful part of this document is the organization of the tables in the CBU submodels. You use this guide to understand the content of the submodels and how the CBU manages the information inside them. You also need to be aware of the restrictions and limitations to customizing the CBU along with the loading policies.

- Project Manager

  As this reference guide contains information about the CBU and its submodels, you will find almost all of the information in this guide as useful when managing your project.

How this Manual is Organized

This manual contains the following chapters:

- **Overview of the CBU**

  This chapter covers the role and content of the CBU.

  It contains information about:

  - The design of the CBU Tables
  - The Design conventions

- **CBU Model**

  This chapter covers the submodels of the CBU.

  For each submodel, it contains:

  - A diagram of the tables and their relationships
  - Description of the submodel
  - Additional information required when working with the submodel

- **Loading the CBU**

  This chapter covers loading information into the CBU.

  It contains information about:

  - The loading policy
  - Loading Dimensions
  - Loading Fact Tables
  - Loading Security Tables

What Typographical Changes and Symbols Mean

This manual uses the following conventions:

TYPEFACE	MEANING	EXAMPLE
Italics	Manuals, topics or other important items	Refer to *Developing Connectors*.
Small Capitals	Software and Component names	Your application uses a database called the CID.
Fixed Width	File names, commands, paths, and on screen commands	Go to `//home/my file`

Obtaining edocs Software and Documentation

You can download edocs software and documentation directly from Customer Central at https://support.edocs.com. After you log in, click on the Downloads button on the left. When the next page appears, you will see a table displaying all of the available downloads. To search for specific items, select the Version and/or Category and click the Search Downloads button. If you download software, an email from edocs Technical Support will automatically be sent to you (the registered owner) with your license key information.

If you received an edocs product installation CD, load it on your system and navigate from its root directory to the folder where the software installer resides for your operating system. You can run the installer from that location, or you can copy it to your file system and run it from there. The product documentation included with your CD is in the Documentation folder located in the root directory. The license key information for the products on the CD is included with the package materials shipped with the CD.

Finding the Information You Need

The product suite comes with comprehensive documentation set that covers all aspects of building solutions based on the edocs Telco Service & Analytics Manager. You should always read the release bulletin for late-breaking information.

Getting Started

If you are new to the edocs Telco Solutions, you should start by reading *Introducing Telco Service & Analytics Manager Applications*. This manual contains an overview of the various components along with the applications and their features. It introduces various concepts and components you must be familiar with before moving on to more specific documentation. Once you have finished, you can read the manual which covers different aspects of working with the application. At the beginning of each manual, you will find an introductory chapter which covers concepts and tasks.

Designing Your Solution

While reading *Introducing Telco Service & Analytics Manager Applications*, you should think about how the different components can address your solution's needs.

You can refer to *Developing Telco Service Manager (TSM)* for information about extending the object model, application security, and other design issues. The *CID Reference Guide* also gives you the information about how the information in your solution is managed and stored.

You can refer to *Developing Telco Analytics Manager (TAM)* for information about customizing the database, synchronizing data with TSM, loading data from external invoice files, and other design issues. The *CBU Reference Guide* also gives you the information about how the information in your solution is managed and stored. You should also read the section on integrating TAM with TSM in *Developing Telco Analytics Manager (TAM)*.

You can also read the introduction of *Developing Connectors* for information about integrating your solution.

Installing Telco Service & Analytics Manager Applications

You should start by reading the Release Bulletin. For detailed installation and configuring information, refer to *Installing Telco Service & Analytics Manager Applications*. This manual covers installing applications on one or more computers. It also contains the information you need to configure the different components you install.

You might also refer to *Developing Telco Service & Analytics Manager Applications* and *Developing Connectors* as these manuals contain information on customizing applications and working with other software.

If you are upgrading, be sure to read *Migrating Telco Service & Analytics Manager Applications*.

Building Your Solution

If you are designing and programming your solution, you have several different sources of information. If you are programming the user interface of the solution, you should read *Developing User Interfaces*. You also refer to the *BLM Specification* and *JSPF specification* for detailed information about programming the user interface. For configuring the various components, you refer to *Installing Telco Service & Analytics Manager Applications* and sections in other documents which deal with the component to configure.

If you are designing and programming TAM, you have several different sources of information. If you are programming the user interface of the solution, you should read *Developing Reports*. You also refer to the *QRA API Specification* and the *QRA Configuration File Reference Documentation* for detailed information about the different components you can use to build reports. For configuring the various components, you refer to *Installing Telco Service & Analytics Manager Applications* and sections in other documents which deal with the component to configure.

If you are working with the business logic of your solution, you should read *Developing Telco Service Manager (TSM)*. You can also refer to the *BLM Reference Guide* for more information about the design and structure of the BLM object model. For information about how this information is stored, you should refer to the *CID Reference Guide* along with the *CID Reference* documentation for your database. In order to develop your application, you most likely will need to install and run the Loopback Connector. This component mimics back-end applications for development purposes. For information about installing and running this component, refer to *Using the Loopback Connector*.

If you are working on the data warehouse side of TAM, you should read *Developing Telco Analytics Manager (TAM)*. For more information about the design and structure of the CBU, you should refer to the *CBU Reference Guide* along with the *CBU Reference* documentation for your database. You should also read *Developing Telco Analytics Manager (TAM)* for information about synchronizing data between the TAM and *Telco Service Manager (TSM)*. In this manual, you will also find information about loading data in both the CBU and the CID.

For more information about integrating your application, you should read *Building Connectors* to learn how Telco Service & Analytics Manager applications work with different software.

Integrating Your Solution

If you are involved in configuring your solution to work with Operation Support Software (OSS), you should read *Building Connectors*. This manual helps you understand the integration architecture and shows you how to build connectors to connect to today's market-leading OSS software. You can also read *Using the Loopback Connector* for information about a connector built for development purposes. Other manuals you can refer to for information about configuring your application include *Introducing Telco Service & Analytics Manager Applications, Developing Telco Analytics Manager (TAM),* and *Developing Telco Service Manager (TSM)*.

Managing Telco Service & Analytics Manager Applications

If you are responsible for managing Telco Service & Analytics Manager applications, you should read the *Installing Telco Service & Analytics Manager Applications* for information about configuring various components and information about working with different application servers. *Administrating Telco Service & Analytics Manager Applications* covers what you need to know about managing your solution at runtime. For information about OSS systems, you should read *Building Connectors*.

If You Need Help

Technical support is available to customers who have valid maintenance and support contracts with edocs. Technical support engineers can help you install, configure, and maintain your edocs application.

edocs provides global Technical Support services from the following Support Centers:

US Support Center

Natick, MA
Mon-Fri 8:30am – 8:00pm US EST
Telephone: 508-652-8400

Europe Support Center

London, United Kingdom
Mon-Fri 9:00am – 5:00 GMT
Telephone: +44 20 8956 2673

Asia Pac Rim Support Center

Melbourne, Australia
Mon-Fri 9:00am – 5:00pm AU
Telephone: +61 3 9909 7301

Customer Central

https://support.edocs.com

Email Support

mailto:support@edocs.com

When you report a problem, please be prepared to provide us the following information:

- What is your name and role in your organization?
- What is your company's name?
- What is your phone number and best times to call you?
- What is your e-mail address?
- In which edocs product did a problem occur?
- What is your Operating System version?
- What were you doing when the problem occurred?
- How did the system respond to the error?
- If the system generated a screen message, please send us that screen message.

- If the system wrote information to a log file, please send us that log file.

If the system crashed or hung, please tell us.

Contents

Preface iii

Overview of the CBU 17

About the CBU 18
About the CBU Tables 19
Fact Tables 20
Dimension Tables 21
Security Tables 23
System Tables 25
CBU Design Conventions 26

CBU Model 29

About the CBU Model 30
Invoices Sub Model 31
Billed Usage Detail Records Sub Model 33
Cost Centers Sub Model 35
Security Sub Model 37
System Sub Model 40

Loading the CBU 41

About the Loading Policy 42
Loading Policy and Sequences 43
Dimension Loading Policy 44
Loading Date and Time Dimensions 44
Loading Billing Period and Business Reference Dimensions 45
Loading Customer Data Dimensions 47
Loading Cost Center Dimensions 48
Fact Table Loading Policy 49

Index 51

CHAPTER 1

Overview of the CBU

In This Section

About the CBU 18
About the CBU Tables 19
CBU Design Conventions 26

About the CBU

The CBU database contains customers billing and usage information.

Users can analyze their invoices using:

- Reference dimensions such as date/time, tariff, and service
- Customer-specific information such as organization views, contracts, and billing accounts

The CBU also comes with built-in security based on roles and scopes. This type of security, which mirrors the security of your TSM, ensures the security and confidentiality of the information in the CBU. User access to the CBU depends on user authentication and the user's assigned roles and scopes.

The CBU is designed to allow users to analyze their own invoices and usage. It is not designed for analysis of the entire customer base.

For more information about:

- The structure and organization of the CBU, refer to the *CBU Reference Guide* and the *CBU Reference Documentation* corresponding to your database.

- Using the administration tools, refer to *Administrating Telco Service & Analytics Manager Applications*.

- Sample data, refer to the CBU demokit readme documentation. This documentation is located in `<home_dir>/samples/cbu/demokit` in a subdirectory corresponding to your database.

About the CBU Tables

The CBU contains the following types of tables:

- Fact tables
- Dimension tables
- Security tables
- System tables

Fact Tables

A fact table contains raw information and is the central table of the CBU. These tables contain the information users want to analyze, such as invoices and usage details.

Dimension Tables

To analyze the raw information in the fact tables, you use dimensions. A dimension is a category of information along with a set of attributes. For example, one of the most common dimensions is time, which you can use to filter the contents of a fact table.

The CBU has the following dimensions:

- **Reference dimensions**

  These dimensions are predefined reference dimensions such as date and time dimensions along with bill periods and other business references.

  For example, when building reports of bill usage detail records in the `NMY_BUDR_FACT` table, you can use the Date and Time dimension to restrict the time period, then apply the Bill Period dimension. Once you have obtained this result, you can then apply a Business Reference such as the service you want in your report.

  Reference dimensions include:

  - Date and Time
  - Bill Period

  The bill period is a period of time that is used to calculate the amount due for services. A bill period has a name and is associated with a bill cycle. A bill period may have a start and end date.

  For instance, a bill period may correspond to a calendar month (January, February, and so on) or may be shorter or longer than that (first half of a month, a day for one time events, and so on.)

- **Business Reference dimensions**

  Business Reference Dimensions are reference dimensions that correspond to information specific to a Telecommunication Service Provider as destination zone, usage type, and so on.

- **Customer data dimensions**

  Customer Data dimensions are dimensions that use information directly associated with a customer. Unlike reference information, which is relatively static, customer data dimensions change and are updated frequently. You use these dimensions to extract information from the fact table that directly concerns the user for your reports.

  For example, when building reports of bill usage detail records in the `NMY_BUDR_FACT` table, you can use the Date and Time dimension to restrict the time period, and then apply the Contract dimension. This allows you to quickly obtain a report for a specific contract.

  Customer Data dimensions include:

  - Contract

- Billing Account
- Cost Center

Security Tables

Security tables contain information relative to access permission.

Security tables include:

- Users
- Actors
- ACL (Access Control List)

Security is handled by affecting roles to users.

A role combined with user scopes define the general access rules of objects. Scopes determine what objects can be accessed according to the user’s member and organization level information.

The available scopes:

- Intra-organization scopes
  - All objects of the organization hierarchy
  - All objects related to the member's level or below
  - All objects owned by the member including associated sub-objects
  - All objects explicitly managed by the member (limited to contracts and members)
- Inter-organization scopes
  - All organizations
  - All organizations managed by the member's level
  - All organizations managed by the top level of the member's organization
  - All organizations managed by the member

All intra-organization scopes can be directly managed in CBU.

For more information on roles, scopes and security, refer to the *BLM Reference Guide*.

There are two methods of managing secure access to CBU objects:

- CBU based security

  You can ensure user confidentiality by implementing security directly in the report SQL query. This query is based on the security tables in the CBU.

  When using this method, the presentation layer must only authenticate the user by using the BLM API or other supported authentication methods.

  You can only use this method for intra-organization scopes and if users are synchronized with in the CBU.

  For more information about how this works, refer to *Creating Reports using SQL* in this manual.

- QRA based security

  You can use the QRA components to manage security by using system prompts. When using this method, you write SQL queries directly accessing the customer dimension table

  For more information about how this works, refer to *Developing Reports*.

System Tables

System Tables contain system information for the CBU or applications accessing the CBU.

CBU Design Conventions

Before you start, it is important to introduce the conventions used by the CBU. This way, when you see diagrams and names of tables, you can easily recognize the contents and use of the different tables.

In the CBU, the contents adhere to the following conventions:

Tables

- Start with the single prefix `NMY_`
- Have a name composed of words in caps letters separated by underscore.
- End with normalized suffixes:
  - `_FACT` Fact tables
  - `_DIM` Dimensions and security tables
  - `_LNK` Link tables
  - `_ACL` Access control list tables
  - `_HLP` Helper tables
  - `_INFO` Information tables

Table Keys

All table key columns names start with the table name (without prefix and suffix).

- Surrogate Key: Internal primary key of a dimension table and always end with suffix `_KEY`
- Business Key: Backend system identifier of a dimension table and always end with suffix `_BIZ`

  Certain business keys can be null.

Attribute Names

To make the CBU model easier to read and understand, standard logical types have been defined to highlight the characteristics and the semantic of attributes. Whenever possible, the attribute naming has also been standardized to enhance the comprehension of the CBU physical model.

The following table describes the following for each the logical types:

- Type
- Description
- Related attribute suffix
- Example of their physical implementation (for Oracle)

LOGICAL TYPE	DESCRIPTION	SUFFIX	PHYSICAL IMPLEMENTATION (ORACLE CONVENTIONS)
T_ACCID	Network ACCess Identifier (example: destination number)	No rule	VARCHAR2(50)
T_BIZ	Nullable business key	_BIZ	VARCHAR2(255)
T_BIZ_AK	Non Nullable business key	_BIZ	VARCHAR2(255)
T_CODE	Attribute storing a value corresponding to a codification	_CODE	VARCHAR2(32)
T_DESC	Any textual attribute fully describing a record.	_DESC	VARCHAR2(255)
T_FLAG	Any boolean attribute	_FLAG	NUMBER(1)
T_INT2	Any integer attribute with a maximum value of 2 digits	No rule	NUMBER(2)
T_INT4	Any integer attribute with a maximum value of 4 digits	No rule	NUMBER(4)

T_INT6	Any integer attribute with a maximum value of 6 digits	No rule	NUMBER(4)
T_KEY	Surrogate key of a dimension table	_KEY	NUMBER(18)
T_KEY_DT	Surrogate key of date dimension table	_DATE_KEY	NUMBER(8)
T_KEY_TM	Surrogate key of time dimension table	_TIME_KEY	NUMBER(4)
T_LABEL	Any textual attribute that can be used to display a record and to select it	_NAME	VARCHAR2(64)
T_MONEY	Any numeric attribute storing amounts value	No rule	NUMERIC(15,3)
T_NAME	Any textual attribute used to display a record	_NAME	VARCHAR2(128)
T_PATH	Complete hierarchical path name of a record (example: cost center path name)	_PATH	VARCHAR2(1024)
T_QTY	Any integer attribute storing a volume	_VOLUME	INTEGER
T_UIDN	Unique ID Number Unique identifier shared by both the end user AND the backend system. Can be null.	_UIDN	VARCHAR2(64)
T_UIDN_AK	Same as T_UIDN but cannot be null	_UIDN	VARCHAR2(64)

CHAPTER 2

CBU Model

In This Section

About the CBU Model 30
Invoices Sub Model 31
Billed Usage Detail Records Sub Model 33
Cost Centers Sub Model 35
Security Sub Model 37
System Sub Model 40

About the CBU Model

The CBU model is divided into the following sub models:

- The Invoices sub model
- The Billed Usage Detail Records sub model
- The Cost Center sub model
- The Security sub model
- The System sub model

Invoices Sub Model



The CBU invoices sub model specifies the following tables:

- Fact tables
  - NMY_MAIN_INVOICE_FACT

    This fact table contains main invoice records. A main invoice is uniquely identified by its billing account and a bill period.

    The invoice number (MAIN_INVOICE_UIDN) is optional.

  - NMY_SUB_INVOICE_FACT

    This fact table contains sub invoice records. A sub invoice is a decomposition of a main invoice for a sub set of contracts billed on the main invoice
    The SUB_ACCT_UIDN attribute allows referencing the sub account related to the sub invoice without requiring its storage.

  - NMY_CONTRACT_INVOICE_FACT

    This fact table contains contract invoice records. A contract invoice is the detail of a main invoice for a specific contract billed on the main invoice.
    The SUB_ACCT_UIDN attribute allows storing the link between the contract invoice and the associated sub invoice if any.

  - NMY_MAIN_CHARGE_FACT

    This fact table contains the detail of every charge of a specific main invoice. An amount value and a volume can be specified for every charge. The real billed period of the charge can also be specified for display purpose.

  - NMY_SUB_CHARGE_FACT

This fact table contains the detail of every charge of a specific sub invoice.

- NMY_CONTRACT_CHARGE_FACT

  This fact table contains the detail of every charge of a specific contract invoice.

- Dimension tables
  - NMY_CONTRACT_DIM

    This dimension table contains contracts.

  - NMY_BILL_ACCT_DIM

    This dimension table contains billing accounts.

  - NMY_BILL_PERIOD_DIM

    This dimension table contains the bill periods. A record must be created for every bill run.

  - NMY_DATE_DIM

    This dimension table contains dates.

  - NMY_CHARGE_TYPE_DIM

    This dimension table contains charge types. A charge type must be specified for every charge.

By default, the model does not manage charge types hierarchy. If required, refer to *Managing Charge Type Hierarchies* in *Developing Telco Analytics Manager (TAM)*.

Billed Usage Detail Records Sub Model



The CBU billed and usage detail records sub model specifies the following tables:

- Fact tables
  - NMY_BUDR_FACT

    This fact table contains billed usage detail records.
  - NMY_MAIN_INVOICE_FACT

    This fact table contains main invoice records.
- Dimension tables
  - NMY_TIME_DIM

    This dimension table contains time periods.
  - NMY_DEST_ZONE_DIM

This dimension table contains destination zone.

- NMY_UDR_TARIFF_DIM

  This dimension table contains the tariffs of Usage Detail Records.

- NMY_UDR_TYPE_DIM

  This dimension table contains the types of Usage Detail Record types.

- NMY_SERVICE_DIM

  This dimension table contains the services.

- NMY_DATE_DIM

  This dimension table contains dates

- NMY_CONTRACT_DIM

  This dimension table contains contracts.

Cost Centers Sub Model



The CBU Cost Centers sub model specifies the following tables:

- Dimension tables
  - NMY_COST_CENTER_DIM

    This dimension table contains cost centers
  - NMY_CONTRACT_DIM

    This dimension table contains contracts.
- Link tables
  - NMY_COST_CENTER_LNK

    This dimension table contains links between cost centers to store the cost center hierarchy.
  - NMY_CC_CONTRACT_LNK

This dimension table contains links between cost centers and contracts to store the contract grouping inside cost centers.

Security Sub Model



To handle security, the CBU uses the following tables:

- **User table** (NMY_USER_DIM)

  The user table stores the users identities of every user accessing the CBU. This table is not provided to perform user authentication. Users must be authenticated by the presentation layer prior to accessing the CBU.

  Feeding this table is only necessary if you want to implement security directly in report SQL queries.

- **Functional Scope link table** (NMY_FUNCT_SCOPE_LNK)

  This table specifies the scope of the user for each reporting function. A reporting function is identified by a function code (example: you can define one function code for each fact table).

  The scope specifies the authorized actors for a specific function code.

  The following elementary scopes can be handled in CBU

  - Member or explicit scope: implemented by the link between the user and the member's user
  - Sub hierarchy scope: implemented by the link between the user and its parent level
  - Organization scope: implemented by the link between the user and its user's organization

  Its possible to merge elementary scopes for one functional code allowing, for example, a user to have a member and a sub hierarchy scope.

- **Role functional scope helper table** (NMY_ROLE_FUNCT_HLP)

  This table specifies the mapping between roles and CBU functional scope. The CID2CBU loader uses this table to create records in the functional scope link table for every user as the following algorithm:

  - ORG_SCOPE_FLAG = TRUE: A link must be created, for the functional code, between the user and his organization in the actor table
  - LEVEL_SCOPE_FLAG = TRUE: A link must be created, for the functional code, between the user and the user's member's parent level
  - MEMBER_SCOPE_FLAG = TRUE: A link must be created, for the functional code, between the user and his member.

If you want to implement security directly in SQL report queries, you must first initialize this table with roles and functional scope you want to manage before being able to synchronize CID users in the CBU.

- **Actor and Actor link tables** (`NMY_ACTOR_DIM` and `NMY_ACTOR_LNK`)

  An actor gives access to a specific list of resources. An actor can be an organization, a level or a member.

  - The `NMY_ACTOR_LNK` table specifies the organization hierarchy. It contains every hierarchy links between parent level (including organization as root level) and all sub hierarchy levels.
  - Member must not be linked to their parent level.

- **ACL tables**

  These tables control access of an actor on the following resources:

  - Billing Accounts
  - Contracts
  - Cost Centers

  The Owner flag in ACL tables allow you to differentiate between objects owned by an actor or explicitly managed by the actor (for example, managing the difference between the owner of a contract and a manager of a contract)

Secured Objects

- Customer data dimensions: The ACL tables with actors secure them.
- Fact tables: There is no direct ACL on fact tables. Relevant customer data dimensions secure them.
  Billing account dimension secures the Main invoice fact table.
  Contract dimension secures the Contract Invoice and Billed Usage Detail Record fact tables
- Time and business reference dimensions: There is no security on these tables.

System Sub Model



The CBU system sub model contains the following tables:

- NMY_VERSION_INFO

  This table contains the CBU version

CHAPTER 3

Loading the CBU

In This Section

About the Loading Policy 42
Loading Policy and Sequences 43
Dimension Loading Policy 44
Fact Table Loading Policy 49

About the Loading Policy

This section outlines the loading policy of the CBU. When you load the CBU, you have to load:

- Customer Dimensions
- Reference Dimensions
- Fact tables
- Security tables

For Customer Dimensions and Security, the CID2CBU loader synchronizes them with the CID. You can also use the CustDim loader to load customer dimensions from invoice files.

You are responsible for loading:

- Fact tables
- Reference Dimensions

Loading Policy and Sequences

Depending on your database, you may need to create sequences or stored procedures when programming the loading of different tables:

- For Oracle, create standard sequence.
- For DB2, create the the `SEQ_<Object_name>_AI_Value` sequence. Be sure to use sequence objects.

  For more information about the sequence objects, refer to the DB2 release notes.
- For SQL Server, create a sequence stored procedure:

  1. Insert a new row in the `KEYSTORAGE` table.

     ```
     insert into KEYSTORAGE(TABLENAME,LASTKEY)
     values('SEQ_<name>_PARAM_VALUE',1000-1)

     go
     ```

  2. Use one of the existing `SP_SEQ_xxxx_AI_VALUE` stored procedure as a template for a creating the new sequence stored procedure `SEQ_<Object_name>_AI_VALUE`

  Example of a stored procedure:

```
insert into KEYSTORAGE(TABLENAME,LASTKEY) values('SEQ_<name>',1000-1)

go

create procedure SP_SEQ_<name> as begin

begin tran

update KEYSTORAGE set LASTKEY=LASTKEY+1 where TABLENAME='SEQ_<name>'

if @@rowcount=1 select LASTKEY from KEYSTORAGE where TABLENAME='SEQ_<name>' else select NULL

commit tran

end

go
```

Dimension Loading Policy

For Dimension tables, the data in the tables can be:

- Pre-loaded. The entries are loaded into the tables before being used by the fact tables.
- On-demand The entries are marked as being needed by the fact loading process. The loading process creates a new entry with a new surrogate key. The attributes are completed afterwards before the system goes back online.
  - The entry can be reconciled with any other data source by using a biz key
  - Post-processing can fill all attributes
- Synchronized with the CID. The entries a user sees are the same in both the CBU and CID.
- Loaded from invoice files (in both the CBU and CID)

Loading Date and Time Dimensions

Date and Time dimensions are static dimensions and are not synchronized. The values can be pre-calculated and loaded before any other information.

The loading of these dimensions is mandatory and they remain constant for the entire lifespan of the Telco Service & Analytics Manager CBU.

Tables:

- `NMY_TIME_DIM`
- `NMY_DATE_DIM`

Loading Guidelines:

1 Define the length of time the Telco Service & Analytics Manager CBU will be on duty in years. The tables will have 365/366 records per year. You can load a few decades. The time table always has 1440 (24 x 60) rows.

Be sure to go far enough in the past to cover the dates of entries in the fact tables.

2 Determine the required attributes for date and time values. *Unused attributes may be omitted (filled with specific constant values to satisfy database constrain*ts).

3 Determine numbering and naming conventions according to your business rules for day, month, quarter, hour, and year.

4 Optionally choose a default/unknown value when date or time information is not provided by facts.

5 Generate and load the data.

Loading Billing Period and Business Reference Dimensions

The Billing Period and Business Reference dimensions can be pre-loaded or loaded on-demand. The contents of this dimension can determine which loading method to use:

- If the content of the dimension does not change often or if you know exactly when it does change (end of a quarter, every night at 3 AM, and so on), use pre-loaded content
- If the content changes frequently or if your application requires up to date information, use on-demand content

The actual loading scenario of these dimensions can be a mix of both solutions and is a compromise between dynamic content and integrity.

Tables:

- `NMY_DEST_ZONE_DIM`
- `NMY_UDR_TARIFF_DIM`
- `NMY_UDR_TYPE_DIM`
- `NMY_SERVICE_DIM`

Loading Guidelines for Pre-loaded Dimensions:

1. Determine the biz key algorithm for the dimension. This key will be used to match the fact data stream and the right entry in the dimension. The linking will be made using the surrogate key.
2. Determine the surrogate key algorithm for the dimension.

   This key MUST not encode any information. You can use a sequence or use a line number from dimension data source (a spread sheet for example). For more information about sequences or stored procedures and your database, refer to *Loading Policy and Sequences*.
3. Determine the entries that will be used by facts.
4. It is recommended to choose a default/unknown value when information is not provided by facts.
5. Decide the name for each entry. This name is used in reports to detail or filter facts.
6. Optionally add a description to entries.
7. Generate and load the data.

Loading Guidelines for On-demand Dimensions:

8. Determine the biz key algorithm for the dimension. This key will be used to match the fact data stream and the right entry in the dimension. The linking will be made using the surrogate key.

9 Create a sequence starting at 1 for each dimension table.

10 When loading new facts, if a business key is not found, create a new entry with the given business key using the sequence to generate the surrogate key. Link the fact to it and notify the request to update this key.

- Decide the name for this new entry.
- Optionally add a description.
- Update the notified entries.

Loading Customer Data Dimensions

The volume of the Customer Data dimensions can be constant or slowly growing.

When deploying your TAM in event mode, you must pre-load this information using the CID2CBU loader. This is due to the sizing requirements. Once loaded, you can implement on-demand loading if required.

When deploying in invoice mode, you can use the CustDim loader to manage loading the customer dimension from invoice files.

For more information about the different modes of deployment, refer to *Introducing Telco Service & Analytics Manager Applications.*

Tables:

- NMY_CONTRACT_DIM
- NMY_BILL_ACCT_DIM
- NMY_USER_DIM
- NMY_FUNCT_SCOPE_LNK
- NMY_ACTOR_DIM
- NMY_ACTOR_LNK
- NMY_BILL_ACCT_ACL
- NMY_CONTRAT_ACL
- NMY_COST_CENTER_ACL

On-Demand Loading Guidelines:

- These guidelines apply to NMY_CONTRACT_DIM and NMY_BILL_ACCT_DIM tables.
- NMY_USER_DIM and NMY_FUNCT_SCOPE_LNK can be only synchronized with information in the CID.
- Create a new entry using a sequence when the business key or the UIDN does not match
- Automatically add attributes if possible: name and UIDN may be provided by the data source (fact stream)
- The New entry will be correlated by the CID2CBU loader during synchronization process with the CID.
- You must also initialize the NMY_ROLE_FUNCT_HLP table. For more information, refer to the *Security Sub Model* section.

For more information about sequences or stored procedures and your database, refer to *Loading Policy and Sequences*.

Loading Cost Center Dimensions

The cost center dimensions do not have to be pre-loaded.

The Telco Service & Analytics Manager CBU fact tables do not depend on the information in the cost center dimensions. This makes on-demand loading irrelevant.

Tables:

- NMY_COST_CENTER_DIM
- NMY_CC_CONTRACT_LNK
- NMY_COST_CENTER_LNK

The CID2CBU loader synchronizes the cost center dimensions with the CID.

Fact Table Loading Policy

Tables:

- NMY_MAIN_INVOICE_FACT
- NMY_CONTRACT_INVOICE_FACT
- NMY_BUDR_FACT

Due to the volume of these tables, you should load these tables by using batches. The batch must cope with on-demand loading for dimensions that implement it.

You must load NMY_MAIN_INVOICE_FACT first. You can then load NMY_CONTRACT_INVOICE_FACT and NMY_BUDR_FACT. The reconciliation is done either on BILL_ACCT + BILL_PERIOD or on MAIN_INVOICE_UIDN if any.

When loading these fact tables:

- If customer data dimension are pre-loaded, new facts that do not match must be discarded.
- If customer data dimension are on-demand, new facts must create any missing entries.

Loading Guidelines:

1. Determine the reconciliation algorithm for each reference dimension keys. Some keys may be degenerated to a single value if it is not used.
2. Determine the reconciliation algorithm for conforming dimension keys. You can use the business key or the UIDN value.
3. Determine the fact attributes that are required by your reports. Unused fact attributes can be ignored, as they are not mandatory.
4. Implement a loading order mechanism taking into account that Contract Invoice and BUDR facts are independent but require Main Invoice facts.
5. In pre-loaded scenario:
   - Load facts from the fact stream.
   - Discard facts when customer data dimension entries are not found.
6. In on-demand scenario:
   - Load facts from the fact stream.
   - Create new customer data dimension entries when necessary.
   - Update newly created dimension entries. This requires populating missing business keys and attributes.

Index

B

BUDR Submodel
- about • 33
- diagram • 33

C

CBU (Communications Billing and Usage) Database
- about • 18
- and Customer Analysis • 19
- and TAM • 18
- Billed Usage Detail Records (BUDR) Submodel • 33
- Cost Center Submodel • 35
- dimension tables • 21
- fact tables • 20
- Invoices submodel • 31
- loading • 42
- Security submodel • 37, 38
- security tables • 23
- submodels • 29
- System submodel • 40
- system tables • 25

COST CENTER CBU Submodel
- about • 35
- diagram • 35

D

DB2
- loading • 43

I

INVOICES CBU Submodel
- about • 31
- diagram • 31

L

Loading
- about • 42
- billing period dimension • 45
- business reference dimensions • 45
- cost center dimensions • 48
- customer data dimensions • 47
- date and time dimensions • 44
- fact table • 49
- sequences • 43

O

Oracle
- loading • 43

S

SECURITY CBU Submodel
- about • 38
- diagram • 37

SQL Server
- loading • 43

SYSTEM CBU Submodel
- about • 38
- diagram • 40

T

TAM
- and the CBU • 18