

**Oracle® Java Micro Edition Software
Development Kit**

Developer's Guide

Release 3.0.5 for Windows

E24265-04

March 2012

This document describes how to use the Java ME SDK plugin for NetBeans.

Copyright © 2009, 2012, Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this software or related documentation is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, the following notice is applicable:

U.S. GOVERNMENT RIGHTS Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, duplication, disclosure, modification, and adaptation shall be subject to the restrictions and license terms set forth in the applicable Government contract, and, to the extent applicable by the terms of the Government contract, the additional rights set forth in FAR 52.227-19, Commercial Computer Software License (December 2007). Oracle USA, Inc., 500 Oracle Parkway, Redwood City, CA 94065.

This software is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications which may create a risk of personal injury. If you use this software in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure the safe use of this software. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software in dangerous applications.

Oracle is a registered trademark of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners.

This software and documentation may provide access to or information on content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

Contents

Preface	xi
Audience	xi
Documentation Accessibility	xi
Conventions.....	xi
Related Documents.....	xi
1 Getting Started	
Quick Start.....	1-1
Tips for Legacy Toolkit Users.....	1-2
Java ME SDK Update Center	1-3
2 Platforms	
Emulation Platforms	2-1
CLDC and MIDP Stack.....	2-1
CDC Stacks.....	2-2
Managing Java Platforms.....	2-3
Java ME Platforms (CLDC and MIDP)	2-3
Java SE and CDC Platforms.....	2-3
Create a Platform for Legacy CDC Projects	2-4
3 Using Sample Projects	
Running a Project.....	3-1
Troubleshooting.....	3-2
Sample Project Overview	3-3
Configuring the Web Browser and Proxy Settings.....	3-5
Resolving Reference Problems.....	3-6
Running MIDP and CLDC Sample Projects.....	3-6
Running the AdvancedMultimediaSupplements Sample Project.....	3-7
Image Effects.....	3-7
Camera.....	3-7
Moving Helicopter.....	3-8
Music Effects.....	3-8
Running the Demos Sample Project.....	3-8
Colors.....	3-9
Properties	3-9

Http	3-9
FontTestlet	3-10
Stock	3-10
Tickets	3-11
ManyBalls	3-12
MiniColor	3-12
Chooser	3-12
HttpExample	3-12
HttpView	3-12
PushExample	3-12
Running FPDemo	3-13
Running Games	3-13
Running Network Demo	3-13
Socket Demo	3-13
Datagram Demo	3-14
Running PhotoAlbum	3-14
Running UIDemo	3-14

4 Creating and Editing Projects

Project Types	4-1
CLDC Projects	4-1
CDC Projects	4-2
The Project Wizard	4-2
Project Template Page	4-2
Name and Location Page	4-3
Choose Project (CDC)	4-3
Platform Selection (CDC)	4-3
WTK MIDP Project Location	4-4
CDC Toolkit Project Location	4-4
Platform Selection Page (CLDC/MIDP)	4-4
Create a CLDC Project	4-4
Create a CDC Project	4-5
Working With Projects	4-6
View Project Files	4-7
Create a New MIDlet	4-8
Import a Legacy MIDP Project	4-8
Import a Legacy CDC Project	4-8
Add Files to a Project	4-9
Search Project Files	4-9

5 Viewing and Editing Project Properties

General Project Properties	5-1
Platform Selection	5-1
Editing Application Descriptor Properties	5-2
CDC Attributes	5-2
MIDP Attributes	5-2
Add an Attribute	5-2

Edit an Attribute	5-3
Remove an Attribute	5-3
MIDlets	5-3
Add a MIDlet.....	5-3
Edit a MIDlet	5-3
Remove a MIDlet	5-3
Change MIDlet Display Order.....	5-4
Push Registry	5-4
Add a Push Registry Entry	5-4
Edit a Push Registry Entry.....	5-4
Remove a Push Registry Entry	5-4
Change Push Registry Display Order.....	5-4
API Permissions	5-4
Adding Permission Requests	5-4
Building a Project	5-5
Configuring Ant	5-5
Compiling.....	5-6
Adding Libraries and Resources.....	5-6
Creating JAR and JAD Files (Packaging).....	5-7
Obfuscating	5-7
Signing	5-7
Signing CDC Projects.....	5-8
Exporting a Key	5-8
Running Settings	5-8
MIDP Project Run Options	5-8
CDC Project Run Options	5-9

6 Running Projects in the Emulator

Emulating Devices	6-1
The Device Manager on Windows	6-1
Viewing Device Properties	6-1
Platform Properties	6-2
Device Information	6-2
Device Properties	6-2
Setting Device Properties	6-2
Opening a Serial Port	6-3
Running a Project from the Device Selector	6-3
Running Projects Simultaneously on a Single Device	6-4
Emulator Features	6-4
Emulator Menus	6-5
Application.....	6-5
Device.....	6-6
Messages.....	6-6
Orientation	6-6
External Events Generator	6-7
Edit	6-7
View	6-7

Help.....	6-7
Adding a Device Instance.....	6-7
7 Searching the WURFL Device Database	
WURFL Search for Devices	7-1
WURFL Search Filtering	7-2
8 Finding Files in the Multiple User Environment	
Switching Users.....	8-1
Installation Directories.....	8-1
NetBeans User Directories.....	8-2
Java ME SDK User Directories	8-3
9 Profiling Applications	
Collecting and Saving Profiler Data in the IDE.....	9-1
Loading a .nps File	9-3
10 Network Monitoring	
Monitor Network Traffic.....	10-1
Filter or Sort Messages	10-2
Save and Load Network Monitor Information.....	10-3
Clear the Message Tree.....	10-3
11 Lightweight UI Toolkit	
LWUIT and the Java ME SDK.....	11-1
LWUIT Resource Editor	11-1
Add a Different LWUIT Library	11-2
LWUIT Demos.....	11-2
12 Security and MIDlet Signing	
Security Domains	12-2
Setting Security Domains	12-2
Specify the Security Domain for an Emulator	12-2
Specify the Security Domain for a Project	12-2
Signing a Project.....	12-3
Sign a CLDC Project With a Key Pair.....	12-3
Sign a CDC Project	12-3
Managing Keystores and Key Pairs	12-3
Working With Keystores and Key Pairs	12-4
Create a Keystore	12-4
Add an Existing Keystore	12-4
Create a New Key Pair	12-5
Remove a Key Pair.....	12-5
Import an Existing Key Pair	12-5
Managing Root Certificates.....	12-6

13 Command Line Reference

Run the Device Manager	13-1
Manage Device Addresses (device-address)	13-1
Emulator Command Line Options	13-2
MIDlet Options	13-2
CDC Options	13-3
Debugging and Tracing Options	13-4
Command Line Profiling	13-4
Build a Project from the Command Line	13-5
Check Prerequisites	13-5
Compile Class Files	13-5
Preverify Class Files	13-5
Packaging a MIDlet Suite (JAR and JAD)	13-6
Command Line Security Features	13-7
Change the Default Protection Domain	13-7
Sign MIDlet Suites (jadtool)	13-7
Manage Certificates (MEKeyTool)	13-8
Generate Stubs (wscompile)	13-9

14 Logs

Device Manager Logs	14-1
Device Instance Logs	14-1

15 JSR Support

JCP APIs	15-1
----------------	------

16 JSR 75: PDA Optional Packages

FileConnection API	16-1
PIM API	16-2
Running PDAPDemo	16-2
Browsing Files	16-2
The PIM API	16-3

17 JSR 82: Bluetooth and OBEX Support

Setting OBEX and Bluetooth Properties	17-1
Running the Bluetooth Demo	17-2
Running the OBEX Demo	17-3

18 JSR 135: Mobile Media API Support

Media Types	18-1
Media Capture	18-2
MM API MIDlet Behavior	18-2
Ring Tones	18-2
Download Ring Tones	18-2

Ring Tone Formats.....	18-2
Running AudioDemo	18-4
Running MMAPIDemos.....	18-4
Simple Tones.....	18-4
Simple Player	18-5
Video.....	18-6
Attributes for MobileMediaAPI.....	18-7
19 JSR 172: Web Services Support	
Generating Stub Files from WSDL Descriptors.....	19-1
Creating a New Mobile Web Service Client	19-2
Run JSR172Demo	19-2
20 JSR 177: Smart Card Security (SATSA)	
Card Slots in the Emulator	20-1
Java Card Platform Simulator (cref)	20-2
Adjusting Access Control	20-2
Specifying PIN Properties.....	20-2
Specify Application Permissions.....	20-3
Access Control File Example	20-4
Running SATSADemos	20-6
APDUMIDlet	20-7
SATMIDlet	20-7
CryptoMIDlet.....	20-7
MohairMIDlet.....	20-8
Running SATSAJCRMIDemo.....	20-8
21 JSR 179 and 293: Location API Support	
Setting the Emulator's Location at Runtime	21-1
Running the CityGuide Sample Project	21-3
Running the CityGuide2_0 Sample Project	21-4
22 JSRs 120 and 205: Wireless Messaging	
Using the WMA Console to Send and Receive Messages.....	22-1
Launching the WMA Console	22-1
WMA Console Interface	22-1
Emulator Phone Numbers	22-2
Sending a Text or Binary SMS Message.....	22-2
Sending Text or Binary CBS Messages.....	22-2
Sending MMS Messages.....	22-3
Receiving Messages in the WMA Console	22-3
Running WMADemo	22-3
WMADemo Push Registry Values	22-3
Running WMADemo OTA.....	22-3
Sending SMS Messages From WMA Console to an Emulator and Back	22-4
Sending CBS Messages from WMA Console to an Emulator.....	22-4

Sending MMS Messages from WMA Console to an Emulator	22-5
Running WMA Tool.....	22-5
smsreceive	22-5
cbsreceive	22-6
mmsreceive	22-6
smssend	22-6
cbssend.....	22-7
mmssend.....	22-7
23 JSR 184: Mobile 3D Graphics	
Choosing a Graphics Mode	23-1
Immediate Mode	23-1
Retained Mode.....	23-1
Quality Versus Speed	23-2
Content for Mobile 3D Graphics.....	23-2
Running Demo3D Samples.....	23-2
Life3D	23-2
RetainedMode	23-3
PogoRoo	23-3
24 JSR 180: SIP Communications	
Understanding the SIP Registrar and Proxy	24-1
Running SIPDemo	24-1
25 JSR 211: Content Handler API (CHAPI)	
Using Content Handlers	25-1
Defining Content Handler Properties.....	25-2
Defining Content Handler Actions	25-3
Running the CHAPIDemo Content Browser.....	25-4
26 JSR 226: Scalable 2D Vector Graphics	
Running SVGDemo.....	26-1
SVG Browser.....	26-1
Render SVG Image.....	26-2
Play SVG Animation.....	26-2
Create SVG Image from Scratch.....	26-2
Bouncing Balls	26-2
Optimized Menu	26-2
Picture Decorator	26-3
Location Based Service	26-4
Running SVGContactList.....	26-5
27 JSR 229: Payment API Support	
Running the Payment Console	27-1
Running JBricks	27-2

28 JSR 238: Mobile Internationalization API (MIA)	
Setting the Emulator's Locale.....	28-1
Using the Resource Manager	28-1
Working With Locales.....	28-2
Working With Resource Files.....	28-2
Working With Resources	28-2
Running i18nDemo	28-3
29 JSR 239: Java Bindings for Open GL ES	
Open GL Overview.....	29-1
30 JSR 256: Mobile Sensor API Support	
Creating a Mobile Sensor Project.....	30-1
Using a Mobile Sensor Project.....	30-2
Creating a Sensor Script File	30-2
SensorBrowser	30-3
Marbles.....	30-3
31 JSR 253: Mobile Telephony API	
The MTA Implementation.....	31-1
Running the MtaDemo	31-1
32 JSR 257: Contactless Communication API	
Using ContactlessDemo	32-1
Tag File Formats.....	32-2
Script Format	32-3
33 JSR 258: Mobile User Interface Customization API	
Running the Customization Sample Project.....	33-1
Revising Sample Project Appearances.....	33-1

Preface

The Oracle® Java ME SDK is mobile application development tool available as a plugin to the NetBeans IDE.

Audience

This document is intended for Java ME application developers.

Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at <http://www.oracle.com/us/corporate/accessibility/index.html>.

Access to Oracle Support

Oracle customers have access to electronic support through My Oracle Support. For information, visit <http://www.oracle.com/support/contact.html> or visit <http://www.oracle.com/accessibility/support.html> if you are hearing impaired.

Conventions

The following text conventions are used in this document:

Convention	Meaning
boldface	Boldface type indicates graphical user interface elements associated with an action, or terms defined in text or the glossary.
<i>italic</i>	Italic type indicates book titles, emphasis, or placeholder variables for which you supply particular values.
<code>monospace</code>	Monospace type indicates commands within a paragraph, URLs, code in examples, text that appears on the screen, or text that you enter.

Related Documents

For more information, see the following documents:

- The supported API documentation links can be found in [Table 15–1, "Supported JCP APIs"](#).

- To see documentation for the Oracle Java Wireless Client and CLDC Hotspot go to <http://download.oracle.com/javame/mobile.html> and look under Documentation for Device Makers
- For SDK, LWUIT, and legacy Sun Java Wireless Toolkit documentation see <http://download.oracle.com/javame/developer.html>.

Getting Started

The Oracle Java Micro Edition (Java ME) Software Development Kit (SDK) is a natural starting point for learning and using Java ME technology. The focus of the SDK is to provide emulation and deployment assistance during the development process. Using this simple yet powerful tool you can create, edit, compile, package, and sign an application. After testing your application in the Java ME SDK emulation environment, you can move to deploying and debugging on a real device.

This SDK provides supporting tools and sample implementations for the latest in Java ME technology. The SDK provides support for recent versions of the Connected Limited Device Configuration (CLDC) and Connected Device Configuration (CDC) platforms.

- [Section 1.1, "Quick Start"](#)
- [Section 1.2, "Tips for Legacy Toolkit Users"](#)
- [Section 1.3, "Java ME SDK Update Center"](#)

As of version 3.0.5, the Java ME SDK is plugin to the NetBeans IDE. In NetBeans the Mobility Pack is a prerequisite to installing the Java ME SDK.

1.1 Quick Start

The Java ME SDK plugin uses NetBeans technology, as described in the online help. These tips offer some hints for getting started as quickly as possible.

- Access the documentation. The online help is the primary documentation for the SDK. Many windows and dialogs feature a help button that opens context-sensitive help in the help viewer.

Select Help > Help Contents to open the JavaHelp Online Help viewer. You can also type F1. Remember to use the search capability and the index to help you find topics.

Note: If you require a larger font size, the help topics are also available as a printable PDF and a set of HTML files.

- Run sample projects. Running sample projects is a good way to become familiar with the SDK.
See [Section 3.1, "Running a Project"](#) for a general overview of how to run a project.
- See the Projects window and the Files window for a visual overview of the logical and physical layout of a project. When viewing items in the tree, use the context

menu (right-click) to see the available actions. See [Section 4.3, "Working With Projects"](#).

- A project has a default device platform property that is used if you run from the toolbar (the green arrow), the Run menu, or the project's context menu. To see a project's default device, right-click the project and select Properties. Choose the Platform category and you see the default device displayed in the Device field. To reset the Device make another choice from the dropdown menu.
To run an application on different devices without changing the default device, right-click on the project and select Run With. Choose a different device and click OK.
- The emulator is an independent process, and once it has started it is a separate process from the build process running in NetBeans. Stopping the build process or closing a project does not always affect the application running in the emulator. You must be sure to terminate the application (the emulator can remain open). See [Section 3.1, "Running a Project"](#).

The SDK provides two unique instances for most devices. For example, DefaultClcdPhone1 and DefaultClcdPhone2 are the same except for the phone number. This means you can perform tests that require two devices (messaging, for example) without customization. If you want to run more than two emulators you can easily make a copy that preserves the settings you require. See [Section 6.9, "Adding a Device Instance"](#).

1.2 Tips for Legacy Toolkit Users

If you used the Sun Java Wireless Toolkit for CLDC or the CDC Toolkit in the past, the advice in [Section 1.1, "Quick Start"](#) still applies because although the user interface is quite different, the project concept is similar. These tips apply legacy terms and ideas to the SDK.

- Runtime focus is less on the project and more on device capabilities and the emulation process.
In legacy toolkits you had to be careful to match the platforms, the APIs, and the capability of the output device. The SDK matches project requirements and device capabilities for you, so mismatches do not occur.

As mentioned in the [Section 1.1, "Quick Start"](#), clicking the green arrow runs the main project. You can right-click any project and select run.

In the device selector you can test many devices without changing the project properties. Right-click any device and choose Run. Only projects that are compatible with the device are shown in the context menu.

- Import applications from legacy toolkits to SDK projects. The installation of the legacy toolkit must exist.

See [Section 4.2.4, "Platform Selection \(CDC\)"](#) and [Section 4.2.6, "CDC Toolkit Project Location"](#).

- Toolkit **settings** are Application Descriptors in the SDK. Right-click on a project and select Properties. Choose the Application Descriptor category.
- Toolkit **utilities** are generally accessible from Tools > Java ME submenu in the NetBeans IDE. For example, the WMA console, the Java ME SDK Update Center and more can be started from the Tools > Java ME submenu.

Select Window > Output in the NetBeans IDE to see the output of the WMA Console or the Payment Console.

- Profiling and Network monitoring utilities are accessed from the Profile > Java ME submenu in the NetBeans IDE.
- The emulator is familiar, but there are some fundamental differences.

It's important to realize that the emulator is a remote process, and once it starts it is independent of the build process running in NetBeans. Stopping the build process or closing a project does not always affect the application running in the emulator. You must be sure to terminate the application from the emulator. For more on this, see [Section 3.1, "Running a Project"](#) and [Section 4.3, "Working With Projects"](#).

In the Wireless Toolkit you could simultaneously run multiple versions of a device because the toolkit would increment the phone number automatically each time you launched a project. Because the emulator is now a remote process, the phone number is a property that must be set explicitly for the device instance.


The SDK provides two unique instances for most devices. For example, DefaultCldcPhone1 and DefaultCldcPhone2 are the same except for the phone number. This means you can perform tests that require two devices (messaging, for example) without customization. If you want to run more than two emulators you can easily make a copy that preserves the settings you require. See [Section 6.9, "Adding a Device Instance"](#).

The emulator has additional display functionality. See [Section 6.7, "Emulator Features"](#).

1.3 Java ME SDK Update Center

The Java ME SDK Update Center supports automatic updating of the entire Java ME SDK plugin, and individual modules within the Java ME SDK. To access the update center, select Tools > Java ME > Java ME SDK Update Center. The update center uses the same technology as the NetBeans Plugins Manager. The update manager works independently so the plugin can be renewed as necessary.

To detect updates, select Tools > Java ME > Java ME SDK Update Center and choose the Available tab. Any available updates will be listed. Choose an update and click Install to update the plugin.



The Java ME SDK supports two technology platforms, also called stacks. They are: [Section 2.1.1, "CLDC and MIDP Stack"](#), and [Section 2.1.2, "CDC Stacks"](#), as discussed in [Section 2.1, "Emulation Platforms"](#).

A project runs on a particular emulation platform. The device manager determines whether a device is appropriate for your project based on the platform, the APIs your application uses, and a set of device properties. If you run an application and an appropriate emulator or device is already running, the SDK automatically installs and runs your application. You don't have to launch the emulator over and over.

On all operating system platforms, you can use the SDK to deploy to a real device using a wireless connection.

2.1 Emulation Platforms

An emulator simulates the execution of an application on one or more target devices. An emulation platform allows you to understand the user experience for an application and test basic portability. For example, a platform enables you to run applications on several sample devices with different features, such as screen size, keyboard, runtime profile and other characteristics.

Java ME SDK provides three well-known emulation platforms: Connected Limited Device Configuration (CLDC) with MIDP, Connected Device Configuration (CDC) with AGUI, and CDC with Personal Basis Profile (PBP). All three platforms include predefined devices with different screen sizes, runtime profiles, and input methods. See [Section 2.1.1, "CLDC and MIDP Stack"](#) and [Section 2.1.2, "CDC Stacks"](#).

2.1.1 CLDC and MIDP Stack

CLDC/MIDP applications conform to both the Connected Limited Device Configuration and Mobile Information Device Profile (MIDP - <http://jcp.org/en/jsr/detail?id=139>). The CLDC/MIDP stack is based on the open source phoneME Feature project at <http://java.net/projects/phoneme>. It supports these technologies:

- CLDC 1.1 and MIDP 2.1
- Optimized Mobile Service Architecture (MSA) stack with extensions (<http://jcp.org/en/jsr/detail?id=248>)
- Java Technology for the Wireless Industry (JTWI) stack (<http://jcp.org/en/jsr/detail?id=185>)
- All the JSRs listed in [Table 15.1, "JCP APIs"](#).

CLDC/MIDP applications are targeted for devices that typically have the following capabilities:

- A 16-bit or 32-bit processor with a clock speed of 16MHz or higher
- At least 160 KB of non-volatile memory allocated for the CLDC libraries and virtual machine
- At least 192 KB of total memory available for the Java platform
- Low power consumption, often operating on battery power
- Connectivity to some kind of network, often with a wireless, intermittent connection and limited bandwidth

Typical devices might be cellular phones, pagers, low-end personal organizers, and machine-to-machine equipment. In addition, CLDC can also be deployed in home appliances, TV set-top boxes, and point-of-sale terminals.

The SDK provides four default emulators to support CLDC:

- ClamshellCldcPhone1
 - CLDC 1.1, MIDP 2.1, MSA 1.1 and extensions for 256, 280, 239 and 229
- DefaultCldcJtwiPhone1 and 2
 - CLDC 1.1, MIDP 2.0, JTWI 1.0
- DefaultCldcMsaPhone1 and 2
 - CLDC 1.1, MIDP 2.1, MSA 1.1
- DefaultCldcPhone1, 2, and 3
 - CLDC 1.1, MIDP 2.1, MSA 1.1 and extensions for 256, 239 and 229

See [Section 4.2.8, "Create a CLDC Project"](#) and [Chapter 6, "Running Projects in the Emulator"](#).

2.1.2 CDC Stacks

A Java ME Platform, Connected Device Configuration (CDC) (<http://jcp.org/en/jsr/detail?id=218>) application is an application targeted for network-connected consumer and embedded devices, including high-end mobile phones, smart communicators, high-end PDAs, and set-top boxes.

Devices that support CDC typically include a 32-bit microprocessor or controller and make about 2 MB of RAM and 2.5 MB of ROM available to the Java application environment.

CDC is based upon the open source project phoneME Advanced, found at <http://java.net/projects/phoneme>. A CDC application conforms to the Connected Device Configuration with a set of profiles that include Personal Basis Profile, Foundation Profile, and AGUI:

- CDC 1.1 with PBP 1.1 (<http://jcp.org/en/jsr/detail?id=217>)
- Foundation Profile 1.1 (<http://jcp.org/aboutJava/communityprocess/final/jsr219/index.html>)
- AGUI 1.0 (<http://www.jcp.org/en/jsr/detail?id=209>)

The SDK provides three default emulators to support CDC:

- Default CdcPbpPhone1

- CDC 1.1, PBP 1.1, Foundation Profile (FP) 1.1
 - VgaAGUIPhone1
 - CDC 1.1, PBP 1.1, FP 1.1 and AGUI 1.0
 - VgaCdcPhone1
 - CDC 1.1, PBP 1.1, FP 1.1

See [Section 4.1, "Project Types"](#) and [Section 6.2, "Viewing Device Properties"](#).

2.2 Managing Java Platforms

To view the Java Platform Manager, select Tools > Java Platforms. Alternatively, right-click on a project, choose Properties from the context menu, select Platform, and select the Manage Emulators button.

The Java Platform Manager is a tool for managing different versions of the Java Development Kit (JDK) and customizing Java platforms that your applications depend on. You can add source files and Javadoc documents to the existing platforms. For Java ME purposes, the platforms are emulators or SDK platforms for mobile devices.

The Java ME SDK pre-registers CDC, J2ME (CLDC and MIDP) and Java SE (the JDK serves as the default platform) for version 3.0.5. Because the Mobility pack is also installed the current Oracle platforms coexist with the legacy Java platforms.

See [Section 2.2.1, "Java ME Platforms \(CLDC and MIDP\)"](#) and [Section 2.2.2, "Java SE and CDC Platforms"](#).

2.2.1 Java ME Platforms (CLDC and MIDP)

To view the Java Platform Manager, select Tools > Java Platforms. The Java ME platform supports CLDC projects. Tabs display the following information for the current platform.

Devices. View all the CLDC devices that the Device Manager has discovered. Click Refresh to reconfigure the platform and refresh the list.

Sources. Add JAR files or source files to the Sources tab to register source code.

Javadoc. Add Javadoc documentation to support any new classes or sources files you have added.

Tools & Extensions. View the tools and extensions for this platform.

2.2.2 Java SE and CDC Platforms

To view the Java Platform Manager, select Tools > Java Platforms. The Java SE platform supports the Java ME SDK. The CDC platform supports the CDC Stack. In the standard Java ME SDK installation the Java SE and CDC platforms have the same options:

Classes. View the platform's classpaths. Add a JAR or folder containing additional classes, moving the classes up and down in the list determines their place in the classpath.

Sources. Add JAR files or source files to the Sources tab to register source code.

Javadoc. Add Javadoc documentation to support any new classes or sources files you have added.

See [Section 2.1.2, "CDC Stacks"](#).

2.2.3 Create a Platform for Legacy CDC Projects

The Java ME SDK version 3.0.5 platform name for CDC does not match the name in the legacy CDC toolkit and the CDC Mobility Pack. The legacy name is "Sun Java Toolkit 1.0 for Connected Device Configuration" while the SDK name is "CDC Oracle Java(TM) Platform Micro Edition SDK 3.0.5". To ensure a successful import, you can create a new platform and give it the legacy name.

The following procedure allows you to import legacy CDC projects without Reference errors (see [Section 3.5, "Resolving Reference Problems"](#)).

1. Select Tools > Java Platforms. Select "CDC Oracle Java(TM) Platform Micro Edition SDK 3.0.5", and in the Classes tab, note the libraries required for the platform.
2. Click Add Platform... and click Next.
3. Select Java ME CDC Platform Emulator and click Next.
4. On the Choose Platform page, select the SDK installation directory. Click Next.
5. On the Platform Name page, type "Sun Java Toolkit 1.0 for Connected Device Configuration" in the Name field. In the Sources tab, add the following libraries: `agui.jar`, `cdc_1.1.jar`, `fp_1.1.jar`, `pbp_1.1.jar`, and `secop_1.0.jar`.

Click Finish, and Close.

See [Section 4.5.2, "Import a Legacy CDC Project"](#) and [Section 3.5, "Resolving Reference Problems"](#).

Using Sample Projects

The Java ME SDK sample projects introduce you to the emulator's API features and the SDK features, tools, and utilities that support the various APIs. These features can help you customize the sample projects or create applications of your own.

The source code for every demonstration application is available in the installation's `\apps` directory. Subdirectories contain projects, and each project has a `src` directory that contains Java programming language source code.

For example, if the SDK is installed in `installdir`, the source code for the SMS sender MIDlet (`example.sms.SMSSend`) in `WMADemo` resides in the following location:

`installdir\apps\WMADemo\src\example\sms\SMSSend.java`

For instructions on running projects, see the following topics:

- [Section 3.1, "Running a Project"](#)
- [Section 3.2, "Troubleshooting"](#)
- [Section 3.3, "Sample Project Overview"](#)
- [Section 3.4, "Configuring the Web Browser and Proxy Settings"](#)
- [Section 3.5, "Resolving Reference Problems"](#)
- [Section 3.6, "Running MIDP and CLDC Sample Projects"](#)

3.1 Running a Project

To run a sample project, go to the Java ME SDK Start Page tab and single-click a sample project name. The project opens in the Project window and starts running in the emulator.

Note: If you can't see the Project window choose Window > Projects. To see console output, select Window > Output > Output.

Follow these steps to run your own projects.

1. Select File > Open Project, and browse to select a project.


The project is added to the Projects window.

2. To run a project, right-click the project and select Run from the context menu.

To run the main project (which is shown in bold text in the Projects window), click the green Run button in the toolbar or press F6.

To set a project as main, right-click the project name and select Set as Main Project.

To run the project on a different device, choose the device in the Device Selector window. Right-click on a device and select Run Project from the context menu. Pull right to see a listing of open projects. Projects that cannot run on the current device are grayed out.



The device emulator window opens with the demo application running.

3. As the sample project runs, you might need to press one of the soft keys below the screen on the left or right side.

You use soft keys to install or launch an application, open a menu, exit, or perform some other action. Some demos include these instructions in the application.

For instructions on running samples, see [Table 3-1](#) or [Table 3-2](#).

4. When you are finished viewing the application, go to the emulator's Application menu and select Exit to close the emulator and stop the execution of the project's build script.

Once the emulator is launched, it is an independent process.

Pressing the red stop button in the Output window terminates the build script, but it does not close the emulator.

Likewise, closing the NetBeans IDE does not affect the emulator. In the emulator, select Application > Exit or press the emulator's exit button (the X) on the upper right.

This ensures that both the emulator process and the project build process close.

3.2 Troubleshooting

Sometimes even a "known good" application, such as a sample project, does not run successfully. The problem is usually your environment.

- Some demonstrations require specific setup and instructions. For example, if a sample uses web services and you are behind a firewall, you must configure the emulator's proxy server settings or web access will fail. See [Section 3.4, "Configuring the Web Browser and Proxy Settings"](#).
- If an application must run over the air (OTA), the SDK automatically installs it in the device instance.

MIDlet Suites use `runMIDlet` to perform the installation.

`installdir\runtimes\cldc-hi\bin\runMidlet.exe`

CDC platforms install applications as follows:

`installdir\runtimes\cdc-hi\bin\cvm.exe`

Because these programs are launched remotely, virus checking software can prevent them from running. If this happens, the project compiles, but the emulator never opens. In the console you see warnings that the emulator cannot connect.

Consider configuring your antivirus software to exclude `runMidlet` and `cvm` from checking.

3.3 Sample Project Overview

The Java ME SDK includes demonstration applications that highlight some of the technologies and APIs that are supported by the emulator.

Most demonstration applications are simple to run. [Section 3.1, "Running a Project"](#) contains instructions for running most demonstrations. Sample projects usually have some additional operation instructions.

[Table 3-1](#) lists all the MIDP/CLDC demonstration applications that are included in this release.

Table 3-1 MIDP/CLDC Sample Projects

Sample	Optional Package	Description	Instructions
Advanced Multimedia Supplements	JSR 234	Demonstrates 3D audio, reverberation, image processing, and camera control.	Section 3.6.1, "Running the AdvancedMultimediaSupplements Sample Project"
AudioDemo	MM API 1.1	Demonstrates audio capabilities, including mixing and playing audio with an animation.	Section 18.4, "Running AudioDemo"
BluetoothDemo	JSR 82	Demonstrates device discovery and data exchange using Bluetooth.	Section 17.2, "Running the Bluetooth Demo"
CHAPIDemo	JSR 211	A content viewer that also uses MediaHandler.	Section 25.4, "Running the CHAPIDemo Content Browser"
CityGuide	JSR 179	A city map that displays landmarks based on the current location.	Section 21.2, "Running the CityGuide Sample Project"
CityGuide2_0	JSR 293	Similar to CityGuide, but with additional Location API 2.0 features.	Section 21.3, "Running the CityGuide2_0 Sample Project"
ContactlessDemo	JSR 257	Emulates detection of RFID tags.	Section 32.1, "Using ContactlessDemo"
Customization	JSR 258	Demonstrates the use of a device's UI themes.	Section 33.1, "Running the Customization Sample Project"
Demo3D	JSR 184	Contains MIDlets that demonstrate how to use 3D graphics, both immediate mode and retained mode.	Section 23.4, "Running Demo3D Samples"
Demos	MIDP 2.0	Includes various examples: animation, color, networking, finance, and others.	Section 3.6.2, "Running the Demos Sample Project"
FPPDemo	CLDC 1.1	Simple floating point calculator.	Section 3.6.3, "Running FPPDemo"
Games	MIDP 2.0	Includes TilePuzzle, WormGame, and PushPuzzle.	Section 3.6.4, "Running Games".
I18nDemo	JSR 238	Includes string sorting, number formatting, and a phrase translator.	Section 28.3, "Running i18nDemo"
JBricks	JSR 229	A game that uses the Payment API for buying extra lives or levels.	Section 27.2, "Running JBricks"

Table 3–1 (Cont.) MIDP/CLDC Sample Projects

Sample	Optional Package	Description	Instructions
JSR172Demo	JSR 172	Demonstrates how to use the JSR 172 API to connect to a web service from a MIDlet.	Section 19.3, "Run JSR172Demo"
LWUITBrowser	N/A	Demonstrates LWUIT features.	Chapter 11, "Lightweight UI Toolkit"
LWUITDemo	N/A	Demonstrates LWUIT features.	Chapter 11, "Lightweight UI Toolkit"
LWUITIODemo	N/A	Demonstrates LWUIT features.	Chapter 11, "Lightweight UI Toolkit"
LWUITMakeover	N/A	Demonstrates LWUIT features.	Chapter 11, "Lightweight UI Toolkit"
LWUITSpeed	N/A	Demonstrates LWUIT features.	Chapter 11, "Lightweight UI Toolkit"
LWUITTimeZone	N/A	Demonstrates LWUIT features.	Chapter 11, "Lightweight UI Toolkit"
LWUITTipster	N/A	Demonstrates LWUIT features.	Chapter 11, "Lightweight UI Toolkit"
MMAPIDemos	MMAPI	Demonstrates MMAPI features, including tone sequences, MIDI playback, sampled audio playback, and video.	Section 18.5, "Running MMAPIDemos"
MtaDemo	JSR 253	Demonstrates how MTA features can be used to simulate telephony actions.	Section 31.2, "Running the MtaDemo"
Multimedia	MMAPI	Demonstrates different video playback formats.	Section 18.5.2.1, "Video"
NetworkDemo	MIDP 2.0	Demonstrates how to use datagrams and serial connections.	Section 3.6.5.1, "Socket Demo" and Section 3.6.5.2, "Datagram Demo"
ObexDemo	JSR 82	Demonstrates device discovery and data exchange using Bluetooth.	Section 17.3, "Running the OBEX Demo"
PDAPDemo	JSR 75	Demonstrates how to manipulate contacts, calendar items, and to-do items. Demonstrates accessing local files.	Section 16.3, "Running PDAPDemo"
PhotoAlbum	MIDP 2.0	Demonstrates a variety of image formats.	Section 3.6.6, "Running PhotoAlbum"
SATSA Demos	JSR 177	Demonstrates communication with a smart card and other features of SATSA.	Section 20.4, "Running SATSA Demos"
SATSAJCRMIDemo	JSR 177	Shows how to use the SATSA-Java Card Remote Invocation method.	Section 20.4.5, "Running SATSAJCRMIDemo"
Sensors	JSR 256	The SensorBrowser and Marbles game demonstrate sensor input.	Section 30.4, "SensorBrowser" and Section 30.5, "Marbles"
SIPDemo	JSR 180	Simple message exchange using SIP.	Section 24.2, "Running SIPDemo"
SVGContactList	JSR 226	Uses SVG to create a contact list displayed with different skins.	Section 26.1.9, "Running SVGContactList"
SVGDemo	JSR 226	Uses different SVG rendering techniques.	Section 26.1, "Running SVGDemo"

Table 3-1 (Cont.) MIDP/CLDC Sample Projects

Sample	Optional Package	Description	Instructions
UIDemo	MIDP 2.0	Showcases the breadth of MIDP 2.0's user interface capabilities.	Section 3.6.7, "Running UIDemo"
WMADemo	WMA 2.0	Shows how to send and receive SMS, CBS, and MMS messages.	Section 22.2.3, "Sending SMS Messages From WMA Console to an Emulator and Back"
XMLAPIDemo	JSR 280	Uses DOM and StAX APIs to create an XML sample and SAX, DOM and StAX APIs to parse the sample.	Follow the instructions the application provides.

[Table 3-2](#) lists the CDC sample projects available in this release.

Table 3-2 CDC Sample Projects

Sample	Optional Package	Description	Instructions
AGUIJava2DDemo	JSR 209	This stand-alone application is a Java SE application adapted for the CDC environment. It demonstrates the graphical and animation capabilities of the Java 2D™ API.	Click the blue arrows to page through the various images and animations. The applications focus on curves. Click the AA icon to see how antialiasing affects appearance.
AGUISwingSet2	JSR 209	Functional tools such as buttons, sliders, and menus implemented with Swing.	Click through the tabs to view the controls and animations.

3.4 Configuring the Web Browser and Proxy Settings

If you are behind a firewall you might need to configure the proxy server so that MIDP applications using web services can succeed.

Note: CDC emulators do not work through a proxy. Communications such as downloading images from the Internet fail on CDC emulators.

The settings are typically the same as those you are using in your web browser.

1. Select Tools > Options.
2. Select the General options icon.
3. In the Web Browser field, choose the browser that will be affected by these proxy settings. Click Edit to add or remove a browser from the dropdown list.
4. Choose a Proxy Setting:
 - No Proxy
 - Use System Proxy Settings
 - Manual Proxy Settings

To set the HTTP Proxy, fill in the proxy server address field and the port number.

The HTTP Proxy is the host name or numeric IP address of the proxy server used to connect to HTTP and FTP sites. The Proxy Port is the port number of the proxy server.


To set the HTTPS or Socks proxy, click More and fill out the Advanced Proxy Options form.

3.5 Resolving Reference Problems

Sometimes when you open a project you can see it has a reference warning. In the Projects tab the project name is red, and the icon shows a warning symbol, as seen below:



Usually this warning means the project refers to a file or library that cannot be found. Right-click on the project and choose Resolve Reference Problems.



The window displays the missing file, the problem, and a possible solution. In this case the project probably used a literal path to the file `keystore.ks`. Clicking the `Resolve...` button opens a file browser so you can find the missing keystore file. The default location is as follows:

`installdir\runtimes\cldc-hi\lib`

Locate and select the file. You receive confirmation that the problem is resolved, and you can now click `Close`.

3.6 Running MIDP and CLDC Sample Projects

This topic gathers MIDP and CLDC samples that aren't discussed in separate chapters. This is the case when a sample uses many JSRs, or when a supported JSR doesn't have any special implementation details.

- [Section 3.6.1, "Running the AdvancedMultimediaSupplements Sample Project"](#)

- [Section 3.6.2, "Running the Demos Sample Project"](#)
- [Section 3.6.3, "Running FPDemo"](#)
- [Section 3.6.4, "Running Games"](#)
- [Section 3.6.5, "Running Network Demo"](#)
- [Section 3.6.6, "Running PhotoAlbum"](#)
- [Section 3.6.7, "Running UIDemo"](#)

For other CLDC demos, see [Table 3-1](#).

3.6.1 Running the AdvancedMultimediaSupplements Sample Project

This MIDlet suite demonstrates the power of JSR 234 Advanced Multimedia Supplements (AMMS). It consists of the following MIDlets:

- [Section 3.6.1.1, "Image Effects"](#)
- [Section 3.6.1.2, "Camera"](#)
- [Section 3.6.1.3, "Moving Helicopter"](#)
- [Section 3.6.1.4, "Music Effects"](#)

3.6.1.1 Image Effects

This MIDlet demonstrates standard image processing operations.

- Select the Image Effects MIDlet and press the Launch soft button.
- Choose input and output image formats, and press Done. The input image and output images are displayed simultaneously.
- Choose an effect from the Menu and click the Done button to apply a transformation, effect or overlay. The source image is shown above and the processed image is shown below. Note that some items, Set Transforms, for example, can perform several operations in a single transaction.

The menu options are as follows:

1. Set Effect Order - Specify the order in which transforms, effects and overlays are applied.
2. Set Transforms - Change width and height scale, border, and rotation options.
3. Set Overlays - Specify the color and orientation of a color block overlay.
4. Reset - Set transforms, effects, and overlays to the initial state.
5. Monochrome Effects - Activate grayscale rendering.
6. Negative Effect - Reverse dark and light areas.

3.6.1.2 Camera

This MIDlet demonstrates how the Advanced Multimedia Supplements provide control of a device's camera. The screen shows the viewfinder of the camera (simulated with a movie). You can use commands in the menu to change the camera settings and take and manage snapshots.

1. Exit - Close this MIDlet and return to the initial window.
2. Snapshot setting - Set whether to display the snapshot on the screen or print it to a file. If the picture is saved to a file, set the snapshot action: Freeze the viewfinder, Freeze and confirm (soft button prompts you to save and you get a confirmation),

Save without freezing (set the picture number). Snapshots are stored in `userhome\javame-sdk\3.0.5\work\emulator_number\appdb\filesystem\root1`.

3. Disable/Enable shutter feedback.
4. Choose exposure modes - Preset modes are auto, landscape, snow, beach, sunset, night, fireworks, portrait, backlight, spotlight, sports, text.
5. Change F_Stop number - 0, 400, 560, 800, 1600.
6. Set flash mode - Off, AUTO, AUTO_WITH_REDEYEREDUCE, FORCE, FORCE_WITH_REDEYEREDUCE, FILLIN.
7. View gallery - View the snapshots stored in:
`userhome\javame-sdk\3.0.5\work\emulator_number\appdb\filesystem\root1`.
8. Zoom settings - digital and optical zoom settings 100-300 in increments of 20.

3.6.1.3 Moving Helicopter

Simulates a helicopter (red dot) flying around a stationary observer (blue dot). Use headphones for best results. You can control the parameters of the simulation with the soft menu options: Volume, Location settings, Spectator orientation, and Distance Attenuation settings. After viewing menu options, press the close button (the X on the right) to return to the helicopter scenario.

With the Location settings be aware that supplying large values for the screen width or flight altitude means the helicopter might be out of range - that is, it will fly off the screen and you might not be able to hear it.

For spectator orientation stereo headphones or speakers will help detect the difference in position, assuming your volume and location settings put the helicopter in audible range. The same is true for the Distance Attenuation settings, which allow you to control the doppler effect.

3.6.1.4 Music Effects

Demonstrates the advanced audio capabilities of the Advanced Multimedia Supplements. As an audio file loops continuously, you can adjust the volume, and reverberation settings.

3.6.2 Running the Demos Sample Project

This demo contains several MIDlets that highlight different MIDP features. Click or use the navigation keys to highlight a MIDlet, then choose the Launch soft key.

- [Section 3.6.2.1, "Colors"](#)
- [Section 3.6.2.2, "Properties"](#)
- [Section 3.6.2.3, "Http"](#)
- [Section 3.6.2.4, "FontTestlet"](#)
- [Section 3.6.2.5, "Stock"](#)
- [Section 3.6.2.6, "Tickets"](#)
- [Section 3.6.2.7, "ManyBalls"](#)
- [Section 3.6.2.8, "MiniColor"](#)
- [Section 3.6.2.9, "Chooser"](#)
- [Section 3.6.2.10, "HttpExample"](#)

- [Section 3.6.2.11, "HttpView"](#)
- [Section 3.6.2.12, "PushExample"](#)

3.6.2.1 Colors

This application displays a large horizontal rectangle that runs the width of the screen. Below, ten small vertical rectangles span the screen. Finally, three horizontal color bars indicate values for blue, green, and red (RGB). Values are expressed as decimal (0-255) or hexadecimal (00-ff) based on the first menu selection.

- To select a vertical bar to change, use the up navigation arrow to move to the color bars. Use the right navigation arrow to highlight a color bar. The large rectangle becomes the color of the selected bar.
- Use the up or down selection arrows to choose the value to change (red, green, or blue). Use the left or right arrow keys to increase or decrease the selected value. The second menu item allows you to jump in increments of 4 (Fine) or 32 (coarse).
- You can change the color on any or all of the vertical bars.

3.6.2.2 Properties

This MIDlet displays your system property values. The output is similar to the following values:

```
Free Memory = 2333444
Total Memory = 4194304
microedition.configuration = "CLDC-1.1"
microedition.profiles = "MIDP-2.1"
microedition.platform = "j2me"
microedition.platform = "en-US"
microedition.platform = "ISO8859_1"
```

3.6.2.3 Http

This test application uses an HTTP connection to request a web page. The request is issued with HTTP protocol GET or POST methods. If the HEAD method is used, the head properties are read from the request.

Preparing to Run the Demo

Before beginning, examine your settings as follows.

- Right-click on Demos and select Properties.
 - Select the Running category.
 - Select Regular Execution.
 - Check Specify the Security Domain and select Maximum.
 - Click OK.
- If you are using a proxy server, you must configure the emulator's proxy server settings as described in [Section 3.4, "Configuring the Web Browser and Proxy Settings"](#). The HTTP version must be 1.1.
- If you are running antivirus software, you might need to create a rule that allows this MIDlet to allow connections to and from a specific web site. See [Section 3.2, "Troubleshooting"](#).

Running the Demo

Launch the Http MIDlet. To test, choose the Menu soft key and choose Get, Post, or Head to test the selected URL.

Http Test returns the information it is able to obtain. If the information fills the screen use the down arrow to scroll to the end. The amount of information depends on the type of request and on the amount of `META` information the page provides. To provide body information or content, the page must declare `CONTENT-LENGTH` as described in RFC 2616.

Using Menu Options

Use the Menu soft key to choose an action. The Menu items vary depending on the screen you are viewing.

- Choose `Qwerty` to set the input type. This activates a submenu with the options `Qwerty`, `123`, `Abc`, `Predict`, and `Symbols`. This choice is present if you have the option to edit a URL (select `Choose`, then click the `Add` soft button).
- Choose `GET` or press the `Get` soft key to retrieve data from the selected URI.
- Choose `POST` to retrieve the post information from the server handling the selected page.
- Choose `HEAD` to retrieve only the `META` information from the headers for the selected URI.
- Select `Choose` to bring up the current list of web pages. You can choose a different page or add your own page to the list. To specify a new URL, choose the `Add` soft button. The screen displays `http://`. Type in the rest of the URL. If necessary select `Qwerty` on the menu and choose a different input method. Make sure to end with a slash `(/)`. For example `http://www.internetnews.com/`. Press the `OK` soft button. The Http Test screen shows your new URL and prompts for an action.

3.6.2.4 FontTestlet

This MIDlet shows the various fonts available: Proportional, Regular, Regular Italic, Bold Plain, and Bold Italic. Choose 1 or 2 from the menu to toggle between the system font (sans serif) and the monospace font.

3.6.2.5 Stock

Like the Http demonstration, this sample uses an HTTP connection to obtain information. Use the same preparation steps as [Section 3.6.2.3, "Http"](#).

Run the Demos project and launch the Stock MIDlet.

By default, the screen displays an empty ticker bar at the top. Below the ticker, the menu list shows four applications: Stock Tracker, What If? Alerts, and Settings. You must add stock symbols before you can use the first three applications.

Add Stock Symbols to the Ticker

To add a stock symbol to the ticker, use the navigation arrows to select `Settings`.

Select `Add Stock`.

The display prompts you to enter a stock symbol. Type `ORCL` and select the `Done` soft key. The stock you added and its current value is now displayed in the ticker. Add a few more stock symbols, such as `IBM` and `HPQ`.

Change the Update Interval

By default the update interval is 15 minutes. Select Updates to change the interval. Use the navigation arrows to select one of Continuous, 15 minutes, 30 minutes, one hour, or three hours. Select the Done soft key.

Remove a Stock

Select Remove a Stock. You see a list of the stocks you have added. Use the navigation keys to select one or more stocks to remove. Choose the Done soft key.

Stock Tracker

Stock Tracker displays a list of the stocks you added and their current values. Stock tracker displays additional information about the selected stock, for example, the last trade and the high and low values.

Choose a stock and press Select.

What If?

What If? is an application that asks for the original purchase price and the number of shares you own. It calculates your profit or loss based on the current price.

Select a stock symbol.

Enter the purchase price and the number of shares, then press Calc.

Alerts

This application sends you a notification when the price changes to a value you specify.

From the main menu, select Alerts.

Select Add.

Choose a Stock. The screen prompts, "Alert me when a stock reaches". Enter an integer.

The alert is placed on the Current Alerts list. To remove an alert, press Remove and select the alert. Choose the Done soft key.

When the value is reached you will hear a ring and receive a message. For example, *Symbol* has reached your price point of *\$value* and is currently trading at *\$current_value*. Once the alert is triggered it disappears from the Current Alerts list.

3.6.2.6 Tickets

This demonstrates how an online ticket auction application might behave. The home screen displays a ticket ticker across the top. Click Done to continue to the Welcome To Tickets page. The Choose a Band field displays BootWare & Friends by default.

Choose a band from the dropdown menu. The available auction appears.

Select Make a Bid from the menu. Use the arrow keys to move from field to field. Fill out each field, then select the Next soft key. The application asks you to confirm your bid. Press the Submit soft key or use the arrow keys to highlight Submit then press Select. You receive a Confirmation number. Click Bands to return to the Bands page.

Select set an alert, select Set an Alert from the soft Menu. In the bid field type in a value higher than the current bid and click the Save soft key. You are returned to the Choose a Band page. You can trigger the alert by making a bid that exceeds your alert value. Your settings determine how often the application checks for changes, so the alert may not sound for a few minutes.

To add a band to the Choose a Band dropdown list, select the Menu soft key and choose Add Bands. Type in a band name or a comma-separated list of names. Choose

the Save soft key. After confirmation you are returned to the Welcome To Tickets page. The added band(s) are displayed at the end of the Choose a Band drop-down menu.

Note, this is only a demonstration. To fully describe the band you must edit the following file:

installdir\apps\Demos\src\example\auction\NewTicketAuction.java.

To remove a band, select the Menu soft key and Remove Bands. Check a box for one or more bands. Choose the Save soft key.

To display the current settings for ticker display, updates, alert volume, and date, select the Menu soft key and choose 6. If desired, use the arrow keys and the select key to change these values. Choose the Save soft key.

3.6.2.7 ManyBalls

This MIDlet starts with one ball traveling the screen. Use the up and down arrows to accelerate or decelerate the ball speed (fps). Use the right or left arrows to increase or decrease the number of balls.

3.6.2.8 MiniColor

This MIDlet sets an RGB value. Use navigation keys to change color values.

Keyboard controls work as you would expect. First cursor up or down to highlight a color, and then use left and right keys to lower and raise the value of the selected color.

3.6.2.9 Chooser

The Chooser application uses a variety of controls to change text color, background color, and fonts.

- Choose Menu > Text Color. Change the color as described for [MiniColor](#) and select the OK soft button.
- Choose Menu > Background Color. Change the color as described for [MiniColor](#) and select the OK soft button.
- Choose Menu > Fonts. You can change the font Face, Style, and Size.

Cursor up and down to highlight a property, then select. The left and right keys jump between lists. Up and down keys move item by item.

Click OK to continue.

3.6.2.10 HttpExample

This sample makes an HTTP communication. A popup confirms the transaction was successful.

3.6.2.11 HttpView

This application displays three predefined URLs.

Choose a URL, and press the soft buttons to cycle through Head, Headers, Requests, and Errors.

Alternatively, Use the menu options.

3.6.2.12 PushExample

This application simulates a feed. As soon as you connect, you receive and display a graphic. Select Done to continue.

3.6.3 Running FPDemo

FPDemo is a simple floating point calculator.

1. Enter a number in the first field.
2. To choose an operator, highlight the drop-down list and click to select. Cursor down to highlight an operator, then click to make a selection.
3. Enter a second value.
4. From the Menu, select Calc or choose 2 to calculate the result.

3.6.4 Running Games

This application features three games: TilePuzzle, WormGame, and PushPuzzle.

TilePuzzle. The desired result, "Rate your mind pal" is shown first. From the soft Menu, select 1, Start. The scrambled puzzle is displayed. The arrow keys move the empty space, displacing tiles accordingly (the arrow key indicates which tile to swap with the space). From the menu you can Reset, or change options.

WormGame. From the soft Menu, select 1, Launch. Use the arrow keys to move the worm to the green box without touching the edge of the window. Once the game is launched, use the soft menu to change game options.

PushPuzzle. Use the blue ball to push the orange boxes into the red squares in the fewest number of moves.

3.6.5 Running Network Demo

This demo has two MIDlets: Socket Demo and Datagram Demo. Each demo requires you to run two emulator instances so that you can emulate the server and client relationship. For example, run the demo on DefaultClcdMsaPhone1 and DefaultClcdMsaPhone2.

3.6.5.1 Socket Demo

In this application one emulator acts as the socket server, and the other as the socket client.

1. In the first emulator, launch the application, then select the Server peer. Choose Start. Depending on your security settings, you might see a message explaining that the demo wants to send and receive data over the network and it might ask, "Is it OK to use network?" Choose Yes. The Socket Server displays a status message when the connection is accepted.
2. In the second emulator, launch the application, select the Client peer, then choose Start. Depending on your security settings, you might see a message explaining that the demo wants to send and receive data over the network and it might ask, "Is it OK to use network?" Choose Yes. Choose Start to launch the client. The Socket Client displays a status message that indicates it is connected to the server. Use the down navigation arrow to highlight the Send box. Type a message in the Send box, then choose the Send soft key.

For example, in the client, type `Hello Server` in the Send box. Choose Send from the menu. The server emulator activates a blue light when the message is received.

3. On the emulator running the Socket Server, the status reads: `Message received - Hello Server`. You can use the down arrow to move to the Send box and type a reply. For example, `Hello Client, I heard you.` From the menu, select Send.

4. Back in the Socket Client, the status is: Message received - Hello Client, I heard you. Until you send a new message, the Send box contains the previous message you sent.

3.6.5.2 Datagram Demo

This demo is similar to Socket Demo. Run two instances of the emulator. One acts as the datagram server, and the other as the datagram client.

1. In the first emulator, launch Datagram Demo, then select the Server peer. Choose Start. Depending on your security settings, you might see a message explaining that the demo wants to send and receive data over the network and it might ask, "Is it OK to use network?" Choose Yes. Initially, the Datagram Server status is Waiting for connection, and the Send box is empty.
2. In the second emulator, launch Datagram Demo, select the Client peer, then choose Start. Depending on your security settings, you might see a message explaining that the demo wants to send and receive data over the network and it might ask, "Is it OK to use network?" Choose Yes. The Datagram Client status is: Connected to server on port 5555. Use the down navigation arrow to highlight the Send box. Type a message in the Send box, then choose the Send from the menu. For example, type Hello datagram server.
3. On the emulator running the Datagram Server, the status displays: Message received - Hello datagram server. You can use the down arrow to move to the Send box and type a reply to the client.
4. In the Datagram Client, the status field displays the message received from the server. The Send box contains the last message you sent.

3.6.6 Running PhotoAlbum

The PhotoAlbum demo displays both static and animated images. When you are displaying an image, you can use the Options soft menu to change the borders. If the image is animated, you can change the speed of the playback.

3.6.7 Running UIDemo

UIDemo showcases a variety of MIDP user interface element implementations. Most elements have some interactive capability (navigate and select) and some allow keypad or keyboard input.

Input interaction is similar across demos. You can choose items from lists or type in data.

This demo implements three list selection methods:

- Exclusive (radio buttons)
- Multiple (check boxes)
- Pop-Up (a drop list).

When entering data, you can use the soft menu to apply one of the following input types to text boxes and fields (note, some elements do not use all input types). When a field is selected, the soft Menu label displays Qwerty. Open the menu and you see the input types numbered 1 through 5.

1. **Qwerty.** Any character on the keyboard
2. **123.** Any numeral

3. **ABC.** Any letter
4. **Predict.** Predicts next character based on prior input
5. **Symbols.** Opens a list of symbols; click to make a selection.
6. **Virtual.** Click on a virtual keyboard to enter data.

The Qwerty, 123, and ABC categories act as filters. For example, if you assign 123 to a field and you type "abc", nothing is entered in the field.

When you finish a demo, select the home button to return to the UIDemo launch page:



CustomItem. This demo features text fields, and text fields in table form. To type in the table, select a cell, then click to open a text entry panel and type your input. From the menu, select OK.

StringItem. Displays labels, a hyperlink, and a button. The soft menu action varies depending on the selected element.

Gauge. Interactive, non-interactive, indefinite and incremental gauges.

Alert. Uses pop-ups to display alerts. Set the alarm type and the length of the timeout from drop lists. Select the alert type and select the Show soft button.

ChoiceGroup. Radio buttons, check boxes, and pop-ups on one screen.

List. Select exclusive, implicit, or multiple to display the list type on a subsequent screen.

TextBox. Use text fields, radio buttons, check boxes, and pop-ups. Select a text box type and press the Show button.

TextField. Text fields with the six input types.

DateField. Set date and time using drop lists.

Ticker. A scrolling ticker.

Creating and Editing Projects

A project is a group of files comprising a single application. Files include source files, resource files, XML configuration files, automatically generated Apache Ant build files, and a properties file.

When a project is created, the SDK performs these tasks:

- Creates a source tree you can examine in the [Section 4.3, "Working With Projects"](#) or [Section 4.4, "View Project Files"](#).
- Sets the emulator platform for the project.
- Sets the project run and compile-time classpaths.
- Creates a build script that contains actions for running, compiling, debugging, and building Javadoc. The build process is controlled by project properties, as described in [Section 5.4, "Building a Project"](#). See also [Section 13.4, "Build a Project from the Command Line"](#).

Java ME SDK and NetBeans create their project infrastructure directly on top of Apache Ant. Java ME SDK projects can be opened and edited in NetBeans, and vice-versa. With the Ant infrastructure in place, you can build and run your projects within the SDK or from the command line.

The SDK provides two views of the project:

- The Projects window provides a logical view of the project.
- The Files window displays a physical view of the project.

Project settings are controlled in the project Properties window. Typically, you right-click on an item or subitem in a tree (a project, a file, or a device) and select Properties.

4.1 Project Types

The CLDC/MIDP platform implements the Mobile Information Device Profile and Connected Limited Device Configuration (JSRs 118 and 139).

The CDC platform is implemented to support Advanced Graphics and User Interface Optional Package for the J2ME Platform, Personal Basis Profile 1.1, and the Connected Device Configuration (JSRs 209, 217 and 218). The AGUI API combines the PBP API and a subset of Java Platform, Standard Edition (Java SE) Swing capabilities.

4.1.1 CLDC Projects

A MIDP application (a MIDlet), is deployed as a MIDlet suite. A MIDlet suite is distributed as a Java archive (JAR) file and a Java Application Descriptor (JAD) file.

The JAR file includes the Java classes for each MIDlet in the suite, Java classes shared between MIDlets, resource files, and other supporting files. The JAR file also includes a manifest describing the JAR contents and specifying attributes the application management software (AMS) uses to identify and install the MIDlet suite.

The JAD file contains attributes that allow the AMS to identify, retrieve, and install the MIDlets in a project. The SDK automatically creates JAD and JAR files when you build the project.

To create a new project, see the NetBeans help topic "New MIDP Project Wizard."

4.1.2 CDC Projects

The CDC platform is implemented to support Advanced Graphics and User Interface Optional Package for the J2ME Platform, Personal Basis Profile 1.1, and the Connected Device Configuration (JSRs 209, 217 and 218). The AGUI API combines the PBP API and a subset of Java Platform, Standard Edition (Java SE) Swing capabilities.

Java ME SDK version 3.0.5 supports CDC projects running as standalone applications. This means the CDC project structure and behavior are much the same as that of CLDC projects.

Note: An Xlet cannot be run standalone. It depends upon an application manager to manage its life cycle (its state) and system services. Xlets are not supported in this release.

A standalone CDC project requires a main application class that includes a method named `main()` that handles class loading, object creation, and method execution. The application interacts directly with the Java runtime environment to manage its own life cycle and system resource needs. When the `main()` method exits, the standalone application terminates.

4.2 The Project Wizard

The project provides a basic infrastructure for development. You provide source files, resource files, and project settings as needed. The SDK provides a wizard for creating new projects quickly and easily using an application template. Most project properties can be edited later by changing the project properties. For more on project properties, see [Chapter 5, "Viewing and Editing Project Properties"](#).

4.2.1 Project Template Page

This is the first page in the New Project wizard.

For MIDP the project options are as follows:

- **MIDP Application.** Create a new MIDP application in a CLDC/MIDP project.
- **Import Wireless Toolkit Project.** Create a project by importing a Sun Java Wireless Toolkit project from an existing toolkit installation.

See [Section 4.2.8, "Create a CLDC Project"](#).

For CDC the project options are as follows:

- **CDC Application.** Create a new CDC application in a CDC project.
- **Import CDC Toolkit Project.** Create a project by importing a CDC Toolkit project from an existing toolkit installation.

See [Section 4.2.9, "Create a CDC Project"](#).

4.2.2 Name and Location Page

Use this form to enter project information. This form is the second page in the New Project wizard. The name and location cannot be changed, but you can view a project's name and location.

Project Name. Enter a project name. If you are importing an existing project this field is pre-populated with the old filename prefixed.

Project Location. The default location is:

C:\Documents and Settings\user\My Documents\NetBeansProjects

Project Folder. The Project Folder value is extrapolated from Project Name and Project Location.

Set as Main Project. Check this box to make the project the Main Project when it is first opened. The Main project is automatically the focus of all actions initiated from the user interface (for example, the actions on the Run menu, which provide the same functionality as clicking icons on the main tool bar).

Create Hello MIDlet. This check box is only visible for a new MIDP project. It inserts sample MIDlet code as a template for your development. You can compile and run the MIDlet immediately.

Create Main Class. This check box is only visible for a new CDC project. Enter the fully qualified name of the main class without the .java extension. For example: com.me.MyClass.

See [Section 4.2.9, "Create a CDC Project"](#).

4.2.3 Choose Project (CDC)

You can view this page in the New Project wizard. The CDC project options are as follows:

CDC Application. Create a new CDC application in a CLDC project.

Import CDC Toolkit Project. Create a project by importing a CDC Toolkit project from an existing toolkit installation.

See [Section 4.2.6, "CDC Toolkit Project Location"](#). See [Section 4.2.9, "Create a CDC Project"](#).

4.2.4 Platform Selection (CDC)

You can view this form in the New Project wizard, or, in the Projects view, right-click a project, select Properties, and select Platform.

These settings help you test how your project runs on devices with different capabilities. Your choice of device limits your choice of Device Configuration and Device Profile.

Emulator Platform. By default you will see two CDC platforms - the 3.0 version installed with the Mobility pack and the 3.0.5 version installed with the Java ME SDK plugin. For the Java ME SDK plugin, choose the 3.0.5 version.

Device. Select a device. Only devices appropriate for the platform appear in the Device drop-down menu. The device selection determines the remaining options.

Device Profile. PBP-1.1 is the only option.

See [Section 4.2.9, "Create a CDC Project"](#).

4.2.5 WTK MIDP Project Location

To see this form, start the New Project wizard and select Import Wireless Toolkit Project.

WTK Location. Browse to select the location of your Sun Java Wireless Toolkit installation. Choose the installation directory.

Detected Applications. When the WTK Location is selected the Detected Applications window displays the available projects. Highlight a project, and click Next.

See [Section 4.5.1, "Import a Legacy MIDP Project"](#).

4.2.6 CDC Toolkit Project Location

To see this form, start the New Project wizard and select Import CDC Toolkit Project.

Project Location. Browse to select the location of your legacy CDC Toolkit project.

See [Section 4.5.2, "Import a Legacy CDC Project"](#).

4.2.7 Platform Selection Page (CLDC/MIDP)

You can view this form in the New Project wizard, or in the Projects view. Right-click a project, select Properties, and select Platform.

These settings help you test how your project runs on devices with different capabilities. Your choice of device limits your choice of Device Configuration, Device Profile, and Optional Packages (if applicable).

Emulator Platform. By default you will see two CLDC platforms - the 3.0 version installed with the Mobility pack and the 3.0.5 version installed with the Java ME SDK plugin. For the Java ME SDK plugin, choose the 3.0.5 version.

Device. Select a device. Only devices appropriate for the platform appear in the Device drop-down menu. The device selection determines the remaining options.

Device Configuration. Select a CLDC version.

Device Profile. Select a MIDP version. The available selections are determined by the Device Configuration.

Optional Packages. This pane is visible when you are viewing an existing project. You can check or uncheck optional packages to approximate device capabilities.

See [Section 4.2.8, "Create a CLDC Project"](#).

4.2.8 Create a CLDC Project

1. Select File > New Project.

The New Project wizard opens. Java ME SDK is the only category.

2. Follow the prompts in the New Project wizard, consulting Help if necessary.
3. To run the new project, follow the steps in [Section 3.1, "Running a Project"](#), except select your new project instead of a sample project.
4. Be sure to exit or close the application when you are finished.

Once the emulator is launched, it runs as an independent process. Pressing the red stop button in the SDK user interface or closing the SDK does not stop the application running in the emulator.

Applications usually provide a way to terminate. For example, most of the samples offer an Exit soft key, or an option in the soft menu. You can close the application and leave the emulator running (so you do not have to wait for the emulator to open the next time you run the project).

If you want to close the emulator and stop the project build process, select Application > Exit.

4.2.9 Create a CDC Project

The SDK provides a wizard for creating new projects quickly and easily. Most project properties can be edited later on. CDC core, FP, and PBP APIs are automatically included in every CDC project.

1. Select File > New Project.

The New Project wizard opens.

2. Follow the prompts in the New Project wizard, consulting help if necessary. See [Section 4.2.4, "Platform Selection \(CDC\)"](#), and [Section 4.2.6, "CDC Toolkit Project Location"](#).

3. **The Name and Location page has the following fields:**

Project Location. Browse to the project location. See the default locations in the table "File Locations".

Project Name. The name you supply is the default name for the Main class, if you use one.

Project Folder. This value is extrapolated from the Name and Location entries.

Set as Main Project. Check this box to set this project as main. Toolbar actions, such as Build and Run, operate on the main project. The main project is displayed in bold font in the project tree.

Create Main Class. If you want to create a sample Main class in the project, check the box and supply a project name. If the box is not checked, the project will not have a Main class.

4. Select platform.

Select the platform, a device, and the profile. Click Finish.

If an AGUI device is selected, the AGUI API is added to the project.

5. To run the new project follow the steps in [Section 3.1, "Running a Project"](#), except you can select your new project instead of a sample project.

When you are finished viewing the application, go to the emulator's Application menu and select Exit to close the emulator and stop the execution of the project's build script.

The SDK provides a wizard for creating new projects quickly and easily. Most project properties can be edited later on. CDC core, FP, and PBP APIs are automatically included in every CDC project.

Note: Once the emulator is launched, it runs as an independent process. Pressing the red stop button in the Output window terminates the build script, but it does not close the emulator. Likewise, closing the SDK does not affect the emulator. In the emulator, select Application > Exit to ensure that both the emulator and the project build process close.

To modify the project, right-click on the project node and select Properties. For more information on project properties, see [Chapter 5, "Viewing and Editing Project Properties"](#).

4.3 Working With Projects

The logical view of the project, shown in the Projects window, provides a hierarchy of sources and resources. Right-click on the project node to see actions related to the project.

New. Opens a form to build a new object for the current project. The new object is placed in the project's file structure by default, but you can control the file name and location. The possible objects are dependent on the currently selected project. For example, if the project is CLDC, the options are MIDlet, Java class, Java package, or Java interface. Selecting New > Other allows you to add different types of files to the project. For a sample procedure, see [Section 19.1, "Generating Stub Files from WSDL Descriptors"](#).

Build. Builds a distribution Java archive (JAR) file. The build process is controlled by project properties, as described in [Section 5.4, "Building a Project"](#).

Clean & Build. Cleans, then builds a distribution JAR file.

Clean. Cleans the build files.

Generate Javadoc. See the online help topic [Generating Javadoc Documentation](#).

Deploy. See the online help topic ["Deploying Java ME Applications"](#).

Batch Build..., Batch Clean & Build..., Batch Clean..., Batch Deploy... See the online help topic ["About Java ME MIDP Projects"](#).

Run. Runs the project with the default device, as specified on the Platform property page. See [Section 5.2, "Platform Selection"](#).

Run With... Run the selected project with a device you choose. This option can override the default device specified in the project properties.

Debug. See the online help topic ["Debugging Tasks: Quick Reference"](#).

Profile. Attach the profiler to the selected project. See [Chapter 9, "Profiling Applications"](#).

Set as Main Project. Make the current project the new main project. Toolbar actions, such as clicking the green Run button, act upon the main project by default.

Unset as Main Project. This option is visible if the selected project is already the main project.

Open Required Projects. Open any projects that the current project is dependent upon.

Close. Close the current project. Be sure that any processes are stopped, as closing a project might not stop the emulator.

The **Source Packages** node encapsulates all the Java packages in the project. Right-click on the Source Packages node and choose New to add a new MIDlet to your application.

The **Resources** node encapsulates all resources and libraries of the active configuration. Right-click the Resources node to add Projects, JARs, folders, and libraries as resources for your application. You cannot add or remove inherited resources.

4.4 View Project Files

The Files window displays a physical view of all project files. Right-click to view project properties or choose an action related to the project.

build. The output directory for the compiled classes listed below. This directory also contains `manifest.mf`, the manifest file that will be added to the JAR file.

- **compiled.** Contains all compiled classes.
- **obfuscated.** Holds the obfuscated versions of the class files.
- **preprocessed.** Holds the source files after they are preprocessed. The files will differ from the original source files if you are using project configurations.
- **preverified.** Holds the preverified versions of the class files. These files are packaged into your project's distribution JAR.
- **preverifysrc.** Versions of the source files before they are preverified.

dist. The output directory of packaged build outputs (JAR files and JAD files). The `dist` directory also contains generated Javadoc documentation.

lib. Contains libraries you have added to the project. See [Section 5.4.3, "Adding Libraries and Resources"](#).

nbproject. The directory that contains the project Ant script and other metadata. This directory contains the following files:

- `build-impl.xml`. The SDK-generated Ant script. Do not edit `build-impl.xml` directly. Always override its targets in `build.xml`.
- `private/private.properties`. Properties that are defined for you alone. If you are sharing the project, any properties you define in this file are not checked in with other project metadata and are only applied to your SDK installation.
- `project.properties`. Ant properties used to configure the Ant script. This file is automatically updated when you configure the project's properties. Manual editing is possible, but it is not recommended.
- `project.xml` and `genfiles.properties`. Generated metadata files. It is possible to edit `project.xml` manually, but it is not recommended. Do not edit `genfiles.properties`.

res. Resource files you have added to the project. See [Section 5.4.3, "Adding Libraries and Resources"](#).

src. The project source files.

build.xml. The build script. This build script only contains an import statement that imports targets from `nbproject/build-impl.xml`. Use the `build.xml` to override targets from `build-impl.xml` or to create new targets.

See also: [Section 4.2.8, "Create a CLDC Project"](#), and [Section 4.2.9, "Create a CDC Project"](#).

4.5 Create a New MIDlet

To create a new MIDlet from the Files view, right-click a project and select New > MIDlet. With this form you can specify the name of the MIDlet and its location within the selected project.

MIDlet Name. The name of the new MIDP class.

MIDlet Class Name. The name that users see when the application runs on a device.

MIDlet Icon. The path to an icon associated with the MIDlet. Users see the icon when the application runs on a device.

Project. Displays the name of the project.

Package. Specifies the location of the MIDlet class. You can select an existing package from the drop down menu, or type in the name of a new package. The new package is created along with the class.

Created File. Displays the name and location of the MIDlet.

When the new MIDlet is created the SDK automatically adds it to the project's Application Descriptor File.

4.5.1 Import a Legacy MIDP Project

If you created a project using the Sun Java Wireless Toolkit for CLDC on Windows or Linux you can import your MIDlets into Java ME SDK projects. You can also use this procedure to create a project based upon a legacy sample project.

1. Select File > New Project.
2. In the Projects area, select Import Wireless Toolkit project. Click Next.
3. Specify the WTK project location.

Use browse to open the directory containing the legacy project.

4. Select a project and click Next.
5. Supply the Project Name, Location, and Folder for the new project.

Note that the default name, project name and folder name are based on the name of the project you are importing. Click Next.

6. Select the Platform type, the default device, and the configuration and profile, if applicable. Click Finish.

Your new project opens in the Projects window.

7. If the legacy project used signing, you must configure the signing properties as described in [Section 12.4, "Managing Keystores and Key Pairs"](#).

4.5.2 Import a Legacy CDC Project

If you created a project using the CDC Toolkit, you can import your applications into Java ME SDK projects. You can also use import to create a project based upon a sample project.

Note: Standalone projects created in the CDC Toolkit can be imported. Xlets cannot be imported.

The CDC platform name for the Java ME SDK version 3.0.5 does not match the legacy platform name in the CDC Toolkit 1.0 and the CDC Mobility Pack. Consequently, you get a reference error when you import a legacy CDC project.

Note: To avoid the reference error, create a platform with the legacy name, as described in [Section 2.2.3, "Create a Platform for Legacy CDC Projects"](#). You only need to do this once.

1. Select File > New Project.
2. In the Projects area select Import CDC Toolkit Project. Click Next.
3. Browse to select the project location.

The wizard detects any applications in the legacy installation and displays their locations on disk. Select a project and click Next.

4. Supply the Project Name, Location, and Folder for the new project. Note, the default name project name and folder name are based on the name of the project you are importing. Click Finish.

The imported project opens in the Projects window.

See also: [Section 2.2.3, "Create a Platform for Legacy CDC Projects"](#), [Section 4.4, "View Project Files"](#).

4.6 Add Files to a Project

For all projects, right-click to use the context menu to add files to a project. Using this method places files in the proper location in project source or resources.

To add a MIDlet, Java class, Java package, Java interface or Other files, right-click the project name or the Source Packages node, choose New, and select the file type.

To add files by format (Project, JAR, Folder, Library) right-click the Resources node and select a format. See [Section 5.4.3, "Adding Libraries and Resources"](#).

4.7 Search Project Files

To search a project's files, right-click on the project and select Find...

The Find in Files utility supports searching a project's file contents or file names. The search input fields supports simple text matching and regular expressions.

Containing Text. The string you are looking for. If File Name Patterns is empty, all files are searched.

File Name Patterns. The files you are searching in. If the Containing Text field is empty you get a listing of files that match the pattern.

The options Whole Words, Match Case, and Regular Expression further restrict the search. Regular Expression Constructs are fully explained in:

<http://download.oracle.com/javase/6/docs/api/java/util/regex/Pattern.html#sum>

Viewing and Editing Project Properties

All projects have properties. Some properties, such as the project's name and location cannot be changed, but other properties can be freely edited as work on your project progresses. To view or edit a project's properties, right-click the project node and select Properties. In the resulting window, you can view and customize the project properties. See the following topics:

- [Section 5.1, "General Project Properties"](#)
- [Section 5.2, "Platform Selection"](#)
- [Section 5.3, "Editing Application Descriptor Properties"](#)
- [Section 5.4, "Building a Project"](#)
- [Section 5.5, "Running Settings"](#)

5.1 General Project Properties

To view the General property page, right-click on a project, choose Properties, and select the General category. The general properties page displays basic project properties. You can set application versioning here, but all other values cannot be edited.

The project name, folder, and source location are set when the project is created. The Application Version Number field displays the version number of the current build.

Application Versioning

The Application Version Counter field displays the next version number to be used. The default advance is 0.0.1. To advance the number beyond this, use the dropdown menu to select a new digit, or enter the value into the field. For example, changing the value to 3 results in a build number of 0.0.3. Changing the value to 100 results in the version number 0.1.0.

Required Projects

This area displays projects you have added to this project. It might be a dependent project or an external library. See [Section 5.4.3, "Adding Libraries and Resources"](#).

5.2 Platform Selection

An emulator platform simulates the execution of an application on one or more target devices. To view this property page, right-click on a project and choose Properties and select the Platform category.

Platform types are listed in the Select Platform Type dropdown. The emulator platform is supplied based on the platform type.

Select a platform type from the dropdown menu.

By default, the devices in the device menu are also suitable for the platform type and emulator platform. The device you select is the default device for this project. It is used whenever you use the Run command. Your device selection influences the Device Configuration and Device Profile options, and the available optional packages.

For CLDC, select the optional packages you want to include in this project. The selected APIs are automatically added to the project's classpath. See [Section 4.2.8, "Create a CLDC Project"](#).

5.3 Editing Application Descriptor Properties

To view this property page, right-click on a project, choose Properties, and select the Application Descriptor category. The Application Descriptor properties page enables adding, editing, or deleting project attributes.

5.3.1 CDC Attributes

To view this property page, right-click on a CDC project and choose Properties. Select the Application Descriptor category.

Application Name. The display name of the application on the target device.

Application Vendor. The company name or author name for the application.

Description. A concise description of the application.

Detail Description. A detailed description of the application.

5.3.2 MIDP Attributes

To view this property page, right-click on a MIDP project and choose Properties. Select the Application Descriptor category, and select the Attributes tab.

The General Attributes table lists the attributes currently contained in the JAD and JAR manifest files:

Type. Lists whether the attribute is required or optional.

Name. The name of the attribute.

Value. The values for each attribute.

To avoid errors in verification:

- Make sure all required attributes have a defined value.
- Do not begin user-defined attribute keys with MIDlet- or MicroEdition-.

5.3.2.1 Add an Attribute

Follow these steps to add an attribute.

1. Click Add... to open the Add Attribute window.
2. Choose an attribute from the Name combo box, or delete the current entry and add your own custom entry.

Note: Do not begin a user-defined attribute name with `MIDlet-` or `MicroEdition-`.

3. Enter a value for the attribute.
4. Click OK.

5.3.2.2 Edit an Attribute

1. Select an attribute.
2. Click Edit... to open the Edit Attribute window.
3. Enter a value for the attribute.
4. Click OK.

API permissions, Push Registry Entries, and API Permissions have their own property pages.

5.3.2.3 Remove an Attribute

Select an Attribute and click Remove to delete it from the list.

5.3.3 MIDlets

To view this page, right-click on a project and choose Properties. Select the Application Descriptor category, and select the MIDlets tab.

The MIDlets table lists the MIDlets contained in the suite and the following properties:

Name. The displayable name of the MIDlet that the user sees when the MIDlet is run on a mobile device.

Class. The Java class for the MIDlet.

Icon. An icon (a .png file), representing the MIDlet that the user sees when the MIDlet is run on a mobile device.

5.3.3.1 Add a MIDlet

1. Click Add... to open the Add MIDlet window.

The window lists the MIDlets available in the project.

2. Enter a name, then select a MIDlet class from the dropdown menu.

You can also choose an icon for the MIDlet from the MIDlet icon dropdown menu.

3. Click OK.

5.3.3.2 Edit a MIDlet

1. Select a MIDlet.
2. Click Edit... to open the Edit MIDlet window.
3. Enter a value for the attribute.
4. Click OK. The revised values are listed in the table.

5.3.3.3 Remove a MIDlet

Select a MIDlet and click Remove to delete it from the list.

5.3.3.4 Change MIDlet Display Order

The list order determines the order in which the MIDlets are displayed.

Select a MIDlet and select Move Up or Move Down to change its position.

5.3.4 Push Registry

To view this page, right-click on a project and choose Properties. Select the Application Descriptor category, and select the Push Registry tab.

See also [Section 5.3.4.1, "Add a Push Registry Entry"](#), [Section 5.3.4.2, "Edit a Push Registry Entry"](#), [Section 5.3.4.3, "Remove a Push Registry Entry"](#), and [Section 5.3.4.4, "Change Push Registry Display Order"](#).

5.3.4.1 Add a Push Registry Entry

1. Click Add... to open the Add Push Registry window.
2. Enter Class Name, Sender IP, and Connection String values.
 - **Class Name.** The MIDlet's class name.
 - **Sender IP.** A valid sender that can launch the associated MIDlet. If the value is the wildcard (*), connections from any source are accepted. If datagram or socket connections are used, the value of Allowed Sender can be a numeric IP address.
 - **Connection String.** A connection string that identifies the connection protocol and port number.
3. Click OK.

The new values are listed in the table. A push registration key is automatically generated and shown as an attribute in the MIDlet suite's Java Application Descriptor (JAD) file.

5.3.4.2 Edit a Push Registry Entry

To make use of the Push Registry, you must also have permission to access the Push Registry API, `javax.microedition.io.PushRegistry`. API permission, are handled in the API Permissions property page ([Section 5.3.5, "API Permissions"](#)).

5.3.4.3 Remove a Push Registry Entry

Select an entry and click Remove to delete it from the list.

5.3.4.4 Change Push Registry Display Order

The list order determines the order in which the MIDlets are displayed. Select an entry and select Move Up or Move Down to change its position.

5.3.5 API Permissions

These properties set permission attributes for protected APIs called by the MIDlet suite. To view this property page, right-click on a project and choose API Permissions. Select the Application Descriptor category, and select the Attributes tab.

See [Section 5.3.5.1, "Adding Permission Requests"](#).

5.3.5.1 Adding Permission Requests

1. Click the Add Button.

The API Permission for API dialog opens.

2. Choose an API from the dropdown list or enter an API into the combo box and click OK.
3. (Optional) In the Requested Permissions table, check the Required box if you want installation to fail in the event that permission cannot be granted.

For more information, see *Security for MIDP Applications* in the MIDP 2.0 (JSR 118) specification, available at:

<http://developers.sun.com/techtopics/mobile/midp/articles/pushreg/>.

5.4 Building a Project

When you build a project, the SDK compiles the source files and generates the packaged build output (a JAR file) for your project. You can build the main project and all of its required projects, or build any project individually.

In general you do not need to build the project or compile individual classes to run the project. By default, the SDK automatically compiles classes when you save them. You can use properties to modify the following build tasks:

- [Section 5.4.2, "Compiling"](#)
- [Section 5.4.3, "Adding Libraries and Resources"](#)
- [Section 5.4.5, "Obfuscating"](#)
- [Section 5.4.4, "Creating JAR and JAD Files \(Packaging\)"](#)
- [Section 5.4.6, "Signing"](#)

5.4.1 Configuring Ant

To view this form, select Tools > Options, select Miscellaneous, and click the Ant tab.

Ant Home. The installation directory of the Ant executable the SDK uses. To change Ant versions, type the full path to a new Ant installation directory in this field or click Browse to find the location. You can only switch between versions 1.5.3 and higher of Ant. The Ant installation directory must contain a `lib` subdirectory which contains the `ant.jar` binary. For example, for the standard Ant 1.7.1 release, the Ant installation directory is `ant\lib\apache-ant-1.7.1`. If you enter a directory that does not match this structure, the SDK gives you an error. You can also specify the following options:

Save All Modified Files Before Running Ant. If selected, saves all unsaved files in the SDK before running Ant. It is recommended to leave this property selected because modifications to files in the SDK are not recognized by Ant unless they are first saved to disk.

Reuse Output Tabs from Finished Processes. If selected, writes Ant output to a single Output window tab, deleting the output from the previous process. If not selected, opens a new tab for each Ant process.

Always Show Output. If selected, the SDK displays the Output window for all Ant processes. If not selected, raises the Output window tab only if the Ant output requires user input or contains a hyperlink. Output that contains hyperlinks usually denotes an error or warning.

Verbosity Level. Sets the amount of compilation output. Set the verbosity lower to suppress informational messages or higher to get more detailed information.

Classpath. Contains binaries and libraries that are added to Ant's classpath. Click Add Directory or Add JAR/ZIP to open the Classpath Editor.

Properties. Configures custom properties to pass to an Ant script each time you call Ant. Click Manage Properties to edit the properties in the property editor. This property is similar to the Ant command-line option, `-Dkey=value`. The following default properties are available:

`${build.compiler.emacs}`. Setting this property to true enables Emacs-compatible error messages.

5.4.2 Compiling

To view this property page, right-click on a project and choose Properties. In the Properties window Build category, choose Compiling.

This page enables you to set the following options:

Generate Debugging Info. If checked, the compiler generates line numbers and source files information. This is the `-g` option in `javac`. If unchecked, no debugging information is generated (the `-g:none` option in `javac`).

Compile with Optimization. If checked, the compiled application is optimized for execution. This is the `-O` option in `javac`. Optimizing can slow down compilation, produce larger class files, and make the program difficult to debug.

Report Uses of Deprecated APIs. If checked, the compiler lists each use or override of a deprecated member or class. This is the `-deprecated` option in `javac`. If unchecked, the compiler shows only the names of source files that use or override deprecated members or classes.

Encoding. Overrides default encoding used by preprocessor and compiler. The default value is the default encoding used by your VM.

5.4.3 Adding Libraries and Resources

To view this property page, right-click on a project and choose Properties. In the Properties window Build category, choose Libraries and Resources.

This page allows you to add a dependent project, libraries, and other supporting files to the current project.

Add Project. The JAR file produced by another project, as well as the associated source files and Javadoc documentation. Adding this item to a classpath sets up a dependency between the current project and the selected JAR file.

Add Library. A Library is a collection of JAR files or folders with compiled classes, which can optionally have associated source files and Javadoc documentation. If the Package checkbox is checked the library is included in the application's JAR file. If it is not checked, the library is copied into the `lib` directory.

Add JAR file. A JAR file created by another project.

Add Folder. The root of a package or directory containing files.

Once a library or resource is added, it is visible in the Libraries and Resources table, which reflects the order of the libraries and resources in the classpath. To change the order in the classpath, select the listing and click Move Up or Move Down. You can also remove libraries and resources from this page.

Each row in the table has a Package check box. If Package is checked, the library or resource is bundled and added to the project JAR file. If Package is not checked, the library or resource is copied to the `lib` subdirectory at build time.

5.4.4 Creating JAR and JAD Files (Packaging)

To view this property page, right-click on a project and choose Properties. In the Properties window Build category, choose Creating JAR.

You can set the following options:

JAD File Name. Name of the JAD file created by the project sources. The file name must have a `.jad` extension.

JAR File Name. Name of the JAR file created by the project sources. The file name must have a `.jar` extension.

Compress JAR. If checked, the JAR file is compressed.

5.4.5 Obfuscating

To view this property page, right-click on a project and choose Properties. In the Properties window Build category, choose Obfuscating.

Use the Obfuscation properties page to set the level of obfuscation for project files.

Move the Obfuscation slider to set the level. The Level Description window describes the impact each level has.

You can add more obfuscation parameters in the Additional Obfuscation Settings window.

5.4.6 Signing

To view this property page, right-click on a project and choose Properties. In the Properties window Build category, choose Signing. These properties allow you to enable signing and assign key pairs to a CLDC project. See [Section 12.1, "Security Domains"](#).

Sign Distribution. Check this box to enable signing for the MIDlet suite. If it is unchecked, this page is disabled.

Keystore. A file that stores one or more key pairs as a keystore (`.ks`) file. The dropdown menu lists all available keystores. Click the Unlock button to unlock a keystore for use.

Alias. A name assigned to a key pair within a keystore. The dropdown menu lists the aliases available for the selected keystore. Click the Unlock button to unlock a key pair for use.

The Certificate Details window provides information about the certificate assigned to the key pair.

Click Open Keystores Manager to manage keystores and key pairs. See [Section 12.4, "Managing Keystores and Key Pairs"](#) and [Section 5.4.8, "Exporting a Key"](#).

Note: CDC projects cannot be signed with the Signing tool. See [Section 5.4.7, "Signing CDC Projects"](#).

5.4.7 Signing CDC Projects

To sign a CDC project use the JDK jarsigner command from the command line. For example:
jarsigner.exe -keystore keystore.ks -storepass keystorepwd
MyCdcApp.jar dummyCA

5.4.8 Exporting a Key

Follow these steps to export a key into an emulator:

- Select Tools > Keystores. This opens the Keystores Manager.
You can add a keystore to the Keystores list at this time. Click the Add Keystore button. After you create the keystore, click New to create a key pair.
- In the Keys area, select a key, and click Export. This opens the dialog Export Key into Java ME SDK/Platform/Emulator.
- Select the target emulator from the Emulator list.
- Select the Security Domain.
- Click Export to export your key pair to the selected emulator.

Your key is added to the bottom of the list in Keys Registered in the Emulator.

The Export window has the following components:

Keystore File. Displays the name of the keystore file to which the key pair belongs. This field cannot be edited.

Key Pair Alias. The name given to the key pair within the keystore. This field cannot be edited.

Certificate Details. Displays the details of the certificate of the key to be exported.

Emulator. The drop-down menu lists all the device emulators available. See [Section 12.1, "Security Domains"](#).

Security Domain. Enables you to select a security domain for the key pair. The menu lists all domains supported by the selected emulator platform.

Keys Registered in the Platform. Lists all keys that have been registered in the selected platform. Click to select the key you want to export.

Delete Key. Deletes a selected key from the Keys Registered in the Emulator window.


Export. Exports the selected key to the selected emulator. The export button is enabled if it is possible to export the key. If a specific key is installed it cannot be installed again.

5.5 Running Settings

To view this property page, right-click on a project and choose Properties. In the Properties window, choose Running. The options shown depend on the platform. See [Section 5.5.1, "MIDP Project Run Options"](#).

5.5.1 MIDP Project Run Options

To set emulator command line options for a MIDP project, type in the command line switches. See [Section 13.3, "Emulator Command Line Options"](#).



For CLDC projects, the Regular execution button is enabled by default. This means the setting for "Specify the Security Domain" applies when the project is run on an emulator. It does not apply for OTA provisioning or an external emulator platform.

If you do not check Specify the Security Domain the project runs with the default that was assigned when the project was created. If you check the box, you can select a domain from the dropdown list. See [Section 12.1, "Security Domains"](#) and [Section 12.2.2, "Specify the Security Domain for a Project"](#).

5.5.2 CDC Project Run Options

For CDC projects you must enter the name of the entry point Java file in the Main Class field. The Main Class Browse button only shows executable classes in the project's source folders. For a CDC project this means all classes with a static main method, or classes extending the Applet or Xlet classes.

Arguments are passed only to the main class, not to individual files. If an Xlet is executed, all arguments are passed to all the Xlets you specify.

For VM options, see [Section 13.3.2, "CDC Options"](#).

Running Projects in the Emulator

The Java ME SDK emulator simulates a CLDC or CDC device on your desktop computer. The emulator does not represent a specific device, but it provides correct implementations of its supported APIs. The SDK uses the device manager to detect devices and displays the available devices in the Device Selector window. See [Section 13.1, "Run the Device Manager"](#).

The Java ME SDK provides default device skins. A skin is a thin layer on top of the emulator implementation that defines the appearance, screen characteristics, and input controls.

If the Device Selector window is not visible, select Window > Device Selector.

6.1 Emulating Devices

The emulator runs applications on an emulated device or a real device. Before you can run an application from the SDK, the Device Manager, which manages both emulated and real devices, must be running. When the Java ME SDK runs, the Device Manager automatically launches and starts detecting devices. The default devices shipped with the SDK are automatically found and displayed in the Device Selector window.


6.1.1 The Device Manager on Windows

The Device Manager is a service and you can see it running in your Windows system tray. In the task manager, the process is labeled `device-manager.exe`.



The Device Manager icon resides in the Windows system tray.

You can right-click on the icon and select Exit to stop the service.



6.2 Viewing Device Properties

The Device Selector window lists all available devices grouped by platform. If this window is not visible, select Window > Device Selector.

If no Java ME platform is registered in NetBeans, the Device Selector displays a node labeled No Device Found. If you see this message at startup, it typically means device discovery is incomplete and you just need to wait a few seconds.

Each sub node represents an emulator skin for a device. Two instances are provided for some CLDC devices, for example, DefaultClcdMsaPhone1 and DefaultClcdMsaPhone2 (DefaultClcdPhone has three default instances). Instances of the same device have the same capabilities but unique phone numbers, making it easy for you to test communication between devices of the same type. If you need an additional device instance, see [Section 6.9, "Adding a Device Instance"](#).

For Device names, see [Section 8.4, "Java ME SDK User Directories"](#). The properties for each device skin are stored in XML files in your user work directory. See [Table 8-1](#).

See also: [Section 6.2.1, "Platform Properties"](#), [Section 6.2.2, "Device Information"](#), and [Section 6.2.3, "Device Properties"](#)

6.2.1 Platform Properties

To view platform properties from the device selector, click on the platform node (for example, CLDC or CDC). The Properties window is, by default, docked in the upper right portion of the user interface. If the Properties window is not visible, select Windows > Properties.

To view the platform properties in a separate window, right-click on the platform node and select Properties. The information in the docked properties window and the separate window is the same.

6.2.2 Device Information

In the Device Selector window, click on a device node. The Device Information tab opens in the central Main window. It displays a picture of the device and displays details, supported hardware capabilities, keyboard support, supported media formats, and the supported runtimes.

6.2.3 Device Properties

In the Device Selector window, click on a device node (such as VgaCdcPhone1) to display the device properties. The Properties window is, by default, docked in the upper right portion of the user interface. If the Properties window is not visible, select Windows > Properties.

6.3 Setting Device Properties

In the Device Selector Window, right-click on a device and select Properties. Any properties shown in gray font cannot be changed. You can adjust the device properties shown in black. Only CLDC options can be adjusted. The CDC options cannot be changed.

Phone Number. You can set the phone number to any appropriate sequence, considering country codes, area codes, and so forth. If you reset this value, the setting applies to future instances. The number is a base value for the selected device.

Heapsize. The heap is the memory allocated on a device to store your applications's objects. The Heapsize property is the maximum heap size for the emulator. You can choose a new maximum size from the dropdown menu.

JAM storage size in KB. The amount of space available for applications installed over the air.

Security Domain. Select a security setting from the dropdown menu. See [Section 12.1, "Security Domains"](#). Applies to CLDC platforms.

Locale. Type in the locale as defined in the MIDP 2.0 specification:
<http://jcp.org/en/jsr/detail?id=118>

Remove MIDlet Suite in execution mode. If this option is enabled, record stores and other resources created by the MIDlet are removed when you exit the MIDlet (assuming the MIDlet was started in execution (non-OTA) mode).

Monitor. Checkboxes for Trace GC (garbage collection), Trace Class Loading, Trace Exceptions, Trace Method Calls, and Enable Tracing for System Classes activate tracing for the device the next time the emulator is launched. The trace output is displayed at runtime in the user interface Output window. Note that Trace Method Calls and Enable Tracing for System Classes return many messages, and emulator performance can be affected.

SATSA. See [Section 20.1, "Card Slots in the Emulator"](#).

Bluetooth. See [Section 17.1, "Setting OBEX and Bluetooth Properties"](#).


Payment. The properties are MCC (mobile country code), MNC (mobile network code), and Passed Transactions Limit. See [Section 27.2, "Running JBricks"](#).

6.4 Opening a Serial Port

In application code, you can use `Connector.open("comm:COM1")` to open a port on the device. On Windows, you can open a serial port such as COM1 or COM2.

6.5 Running a Project from the Device Selector

The SDK determines which open projects are suitable for a device. Right-click on the device and select a project from the context menu. If projects are not suitable they are displayed in gray font.



You can also launch the emulator to run a project from the command line, as explained in [Section 13.3, "Emulator Command Line Options"](#).

6.6 Running Projects Simultaneously on a Single Device

CLDC-based devices are capable of running multiple virtual machines. You can test this behavior in the emulator. Be sure the output window is visible in the SDK (select Window > Output > Output). To test this feature, follow these steps:

1. Open the sample projects Games and AudioDemo.
2. In the device selector, choose an MSA-compliant device and run Games. When the emulator launches run AudioDemo on the same device.
As each MIDlet loads, the AMS automatically installs it.
3. In AudioDemo, launch the Audio Player, and play the JavaOne theme.
Select AudioPlayer, then from the soft menu, select 1, Launch. Select JavaOne Theme and press the Play soft button.
4. In the emulator, choose Application > AMS Home, or press F4.
Select Games. From the soft menu, select 1, Open. The music continues to play while you are able to simultaneously launch and play games.
5. Select Application > AMS Home, or press F4. Highlight AudioSamples, and from the soft menu, select 2, Bring to foreground. Press the Pause soft key. The music stops playing.
6. Select Application > AMS Home, or press F4. Highlight AudioSamples and from the soft menu, select 1, Open. Select Bouncing Ball from the list and press the Launch soft button. Select MIDI background and press the Play soft button.
7. Select Application > AMS Home, or press F4. Select Application > Switch Running MIDlet. Select Audio Player and press the Switch to soft button. You can press the Play soft button to resume the Audio Player.

6.7 Emulator Features

[Figure 6-1, "Emulator Features"](#) shows common emulator features available on emulators for the CLDC platform.

Device Name. Shown in the upper window frame. See [Table 8-1, "Device Names"](#).


Transmission Indicator. On the upper left of the emulator image, this blue light turns on when a transmission is occurring. Typically you see it when an application is installed over-the-air, or when a message is being sent or received. For example, when you receive a message from the WMA console.

Menus. See [Section 6.8, "Emulator Menus"](#).

Device ID. See [Table 8-1, "Device Names"](#).

Exit Button. Pushing the button on the upper right of the emulator image has the same effect as selecting Application > Exit.

Emulator Status Bar. Information about the current system state is shown in the status bar at the bottom of the emulator window.

Figure 6–1 Emulator Features

6.8 Emulator Menus

The emulator for the CLDC platform has Application, Device, Edit, View, and Help menus.

The emulator for the CDC platform has Application, Device, View, and Help menus. The View and Help menus are the same on CDC and CLDC platforms. For CDC, the Device menu is not populated, and Application menu contains only the Exit option.

6.8.1 Application

The Application menu is fully populated for the CLDC platform. The Application options are as follows:

Option	Accelerator	Description
Run MIDlet suite		Emulator interface for launching MIDlets. To run sample applications, choose the <code>apps*\dist*.jar</code> file.
AMS Home	F4	Exit the current application and return to the Application Management Software home.
Stop	F10	Stops the currently running MIDlet.
Change Locale		<p>This option only works with localized MIDlets.</p> <p>Enter a locale identifier. The format is similar to Java SE 6, as follows:</p> <p>2-letter-lang-code <i>separator</i> 2-letter-country-code</p> <p>For example, en-US, cs-CZ, zh-CN, ja-JP. The separator can be a dash or an underscore.</p>
Resume	F6	Resume a suspended application.
Suspend	F5	Pause a running application.
Switch Running MIDlet	F7	When you have multiple MIDlets running, toggle between them. You see a list of running MIDlets and you can choose the one you want to view. See Section 6.6, "Running Projects Simultaneously on a Single Device" .
Exit	Exit button on emulator upper right	Close the emulator process and stop the build process (or processes).

6.8.2 Device

This menu is available on CLDC platforms. For CDC emulators the menu exists, but it is empty.

6.8.2.1 Messages

Choose Device > Messages to see what is written in the message area. This is the emulator's Inbox. The Inbox displays messages that are addressed to the device, not an application on the device. The

- MMS messages without an AppID in the address
- SMS messages without a port in the address
- SMS text messages with a port in the address, provided there is not a Java ME application listening on the specified port.

To test sending messages to the inbox use the WMA Console in Netbeans, or from the command line, use `wma-tool.exe`. Note that `wma-tool.exe` requires an AppID for MMS, so it can't be used to send a message. For SMS a port number is required, but you can use 0 for the port to send a message to the inbox.

6.8.2.2 Orientation

Use this feature to test your application's ability to display in portrait and landscape formats. The default is 0 degrees. Change the orientation to 90, 180, or 270 degrees. You can also rotate 90 degrees clockwise (F8) or counterclockwise (F9) from the current position.

6.8.2.3 External Events Generator

The External Events Generator allows you to interact with an application by injecting events. The interaction may be through a user interface, or through a script file. The following menu options each have a tab on the External Events Generator. The use of the External Events Generator is addressed in the discussion for each JSR.

- **Contactless Communication.** See [Section 32.1, "Using ContactlessDemo"](#).
- **Customization.** [Section 33.2, "Revising Sample Project Appearances"](#).
- **File Connection.** [Section 16.1, "FileConnection API"](#).
- **Location.** [Section 21.1, "Setting the Emulator's Location at Runtime"](#).
- **Mobile Telephony.** [Section 31.2, "Running the MtaDemo"](#).
- **Payment Transactions.** [Section 27.2, "Running JBricks"](#).
- **Sensors.** [Section 30.2, "Using a Mobile Sensor Project"](#), [Section 30.3, "Creating a Sensor Script File"](#).

6.8.3 Edit

The Edit menu provides basic editing utilities for the CLDC platform.

Option	Accelerator	Description
Copy	CTRL-C	Copy selected material to the paste buffer.
Cut	CTRL-X	Move selected material to the paste buffer.
Paste	CTRL-V	Insert the contents of the paste buffer.

6.8.4 View

The View menu is available for both CLDC and CDC platforms. The only View option available is Always On Top.

Option	Description
Always On Top	Keeps the emulator in the foreground. This is especially useful when you are running multiple emulator instances and you want to see them all and send messages between devices.

6.8.5 Help

The Help menu displays an abbreviated helpset specifically for the emulator window.

6.9 Adding a Device Instance

As described in [Section 6.2, "Viewing Device Properties"](#), a particular device emulator can have more than one instance, and each instance is differentiated by a number appended to the emulator name, as seen in [Table 8-1](#). Each device instance is stored in a numbered directory. See [Section 8.4, "Java ME SDK User Directories"](#).

To create your own instance, follow these steps:

1. Close the Java ME SDK.

2. In the device-adapter directory (see [Section 8.3, "NetBeans User Directories"](#)), copy a numbered directory and rename it with the next number in the sequence, for example, 11 (see [Table 8-1](#)).
3. In the copied directory, open the `properties.xml` file and change the `name` property string to a unique name.
You can also change the values in `device.properties`.
4. In the system tray, right-click on the Device Manager icon and select Exit from the context menu.
5. Start the Java ME SDK.

In the Device Selector you see a new node named Other. All your custom devices are listed here. To assign this device to a project, right-click the project, select Properties, and choose Platform. Your instance appears in the Device drop list.

You can also edit the device adaptor to create a new instance. For example, to create a second instance of the ClamshellCldcPhone, follow these steps:

1. Go to the device adapter directory (see [Section 8.4, "Java ME SDK User Directories"](#)).
2. Make a copy of `1.bean`, and name it `2.bean`.
3. Edit `2.bean` to change the device number to 2. For example, `ClamshellCldcPhone2`.
4. Exit the SDK and exit the Device Manager.
5. Start the SDK. `ClamshellCldcPhone2` is listed in the Other category.

Searching the WURFL Device Database

The Wireless Universal Resource File (WURFL) is an XML file that acts as a global database of mobile device capabilities. WURFL is an open source project at <http://wurfl.sourceforge.net/>. The WURFL DB (<http://www.wurflpro.com/>) is a web-based interface that allows WURFL contributors to add or change device information in the WURFL.

The SDK uses a WURFL module to discover devices based on API support or on physical characteristics such as physical memory size or display size.

7.1 WURFL Search for Devices

Follow these instructions to search for devices.

1. Select Tools > Java ME > Device Database Search.

The WURFL Device Search tab opens in the main window.

2. Check Use Filter to see search options.

If you do not check Use Filter, all devices in the database are listed. See [Section 7.2, "WURFL Search Filtering"](#).

3. Make a selection from the dropdown menu on the left.

If applicable, the center dropdown displays a list of conditions. The menu on the right displays a value.


4. To add another search criteria, click the + button.

Click the - button to remove a search setting.

5. Click the Search button.

The search returns devices that match all the chosen criteria. The results are not case sensitive.

6. Click on a device to view its properties on the right, as shown below.



The screenshot shows the Wurfl Device Search interface. At the top, there are tabs for "Wurfl Device Search" and "Start Page". Below the tabs is a toolbar with icons for back, forward, and search. A checkbox labeled "Use Filter" is checked. The "Filter" section contains two dropdowns: "Supported APIs" and "Heap Size". The "Supported APIs" dropdown has several options: MIDP 2.0, CLDC 1.1, MMAPI 1.0, MMAPI 1.1, and WMAPI 1.0. The "Heap Size" dropdown shows "is greater than" and the value "900000". A "Search" button is located below the filter section. The main area displays a table of devices. The table has two sections: "16 devices found" and "P900". The "16 devices found" section shows a list of devices with their vendors: CF75 (Siemens), SK65 (Siemens), C72 (Siemens), SGH-D600 (Samsung), A1000 (Motorola), A780 (Motorola), i730 (Motorola), i830 (Motorola), E680, E1000, V980, S700, P900 (highlighted in blue), Z1010, Z500, and P30 (BenQ). The "P900" section shows a detailed table of properties and values for the P900 device.

Property	Value
max_image_width	186
max_image_height	227
colors	65536
j2me_midp_2_0	true
j2me_jtwi	true
j2me_mmaapi_1_0	true
j2me_wmapi_1_0	true
j2me_btapi	true
j2me_heap_size	16777216
j2me_canvas_height	253
j2me_bits_per_pixel	16
j2me_bits_per_pixel	16
j2me_http	true
j2me_https	true
j2me_socket	true

See [Section 7.2, "WURFL Search Filtering"](#).

7.2 WURFL Search Filtering

As discussed in [Section 7.1, "WURFL Search for Devices"](#), you can use the filter to set search constraints. If Use Filter is not checked all devices are listed. If Use Filter is checked, you must set at least one constraint.

Supported Properties

This utility searches on a predefined list of constraints that have corresponding properties in the Java ME SDK.

- **Supported APIs**

You can check the APIs you want. Note, checking an API does not exclude APIs that are not checked.

- MIDP 1.0, MIDP 2.0
- CLDC 1.0, CLDC 1.1MMAPI 1.0, MMAPI 1.1
- WMAPI 1.0, WMAPI 1.1, WMAPI 2.0

- Bluetooth API
- 3D API
- Localization API
- Vendor
- Device
- Resolution Width/Height
 - The device resolution.
- Maximum Image Width/Height
 - The maximum image size that the device can display.
- Physical Memory Size
 - The built-in memory size.
- Heap Size
 - Memory limit in bytes at runtime.
- Number of Colors
 - The number of colors the device's display supports.
- Supports Wi-Fi
- Supported Image Formats
 - Check the image type. Unchecked types might still be supported.
 - bmp
 - jpeg
 - gif

To see the full list of WURFL constraints, go to:
http://wurfl.sourceforge.net/help_doc.php.

See also [Section 7.1, "WURFL Search for Devices"](#).

Finding Files in the Multiple User Environment

The Java ME SDK can be installed on a system running a supported operating system version. All users with an account on the host machine can access the SDK. This feature is called the Multiple User Environment.

Note: The Multiple User Environment supports access from several accounts. It does not support multiple users accessing the SDK simultaneously. See [Section 8.1, "Switching Users"](#).

To support multiple users the SDK creates an installation directory that is used as a source for copying. This document uses the variable *work* to represent the SDK working directory and *installdir* to represent the installation directory. Each user's personal files are maintained in a separate working directory named `javame-sdk` that has a subdirectory for each version installed.

- [Section 8.2, "Installation Directories"](#)
- [Section 8.3, "NetBeans User Directories"](#)

To locate logs, see [Section 14.1, "Device Manager Logs"](#), and [Section 14.2, "Device Instance Logs"](#).

8.1 Switching Users

Multiple users cannot run the SDK simultaneously, but, you can run the SDK from different user accounts on the SDK host machine. When you switch users, you must close the SDK and exit the Device Manager, as described in [Section 6.1.1, "The Device Manager on Windows"](#). A different user can then launch the SDK and own all processes.

8.2 Installation Directories

The Java ME SDK installation directory structure conforms to the Universal Emulator Interface Specification (http://java.sun.com/j2me/docs/uei_specs.pdf), version 1.0.2. This structure is recognized by all IDEs and other tools that work with the UEI. The installation directory has the following structure:

- `apps`. Contains examples for supported platforms:
 - CDC and AGUI: AGUIJava2DDemo and AGUISwingSet2.
 - CLDC and MIDP: all other applications.

- bin. The bin directory contains the following command line tools. The default location of the bin directory is:
installdir\bin
 - cref. Java Card simulator for working with SATSA JSR 177. See [Section 20.2, "Java Card Platform Simulator \(cref\)"](#).
 - device-address is a tool for viewing, adding, and removing devices that the SDK is not able to discover automatically. See [Section 13.2, "Manage Device Addresses \(device-address\)"](#).
 - device-manager. The device manager is a component that must be running when you work with Java ME SDK. After installation it starts as a service, and it will automatically restart every time your computer restarts. See [Section 6.1, "Emulating Devices"](#).
 - emulator. UEI compliant emulator. See [Section 13.3, "Emulator Command Line Options"](#).
 - jadtool. Tool for signing MIDlets. See [Section 13.6.2, "Sign MIDlet Suites \(jadtool\)"](#).
 - mekeytool. Management of ME keystores. See [Section 13.6.3, "Manage Certificates \(MEKeyTool\)"](#).
 - payment-console. Minimalistic console for viewing payment transactions. An equivalent tool exists in the Java ME SDK user interface.
 - preverify. The Java ME preverifier.
 - resourcesmanager. A tool for managing JSR 238 resource bundles. An equivalent tool exists in the Java ME SDK user interface.
 - wma-tool. A command line tool for sending and receiving SMS, CBS, and MMS messages. See [Section 22.3, "Running WMA Tool"](#).
 - wscompile. Compiles of stubs and skeletons for JSR 172. See [Section 13.7, "Generate Stubs \(wscompile\)"](#).
- docs. Release documentation.
- ide-support. The NetBeans integration file for Java ME SDK Plugin.
- legal. License and copyright files.
- lib. JSR JAR files for compilation.
- pkg-toolkit. Packaging utility files.
- runtimes. CDC and CLDC runtime files.
- toolkit-lib. Java ME SDK files for configuration and definition of devices and UI elements. Executables and configuration files for the device manager and other SDK services and utilities.

8.3 NetBeans User Directories

These are the default NetBeans user directories.

- NetBeans default project location:
C:\Documents and Settings\user\My Documents\NetBeansProjects
- To see the NetBeans Userdir, select Help > About in the main window. The location is:

C:\Documents and Settings\user\.netbeans\version

8.4 Java ME SDK User Directories

- This documentation sometimes uses *userhome* to represent the root location of user files.

The javame-sdk directory contains device instances and session information. If you delete this directory, it will be recreated automatically when the device manager is restarted.

C:\Documents and Settings\user\javame-sdk\version

- Device working directories

C:\Documents and Settings\user\javame-sdk\version\work

The numbered subdirectories each correspond to an emulator, as described in [Table 8-1](#).

Table 8-1 Device Names

Emulator #	Device	Platform
0	ClamshellCldcPhone1	CLDC
1	DefaultCdcPbpPhone1	CDC
2	DefaultCldcJtwiPhone1	CLDC
3	DefaultCldcJtwiPhone2	CLDC
4	DefaultCldcMsaPhone1	CLDC
5	DefaultCldcMsaPhone2	CLDC
6	DefaultCldcPhone1	CLDC
7	DefaultCldcPhone2	CLDC
8	DefaultCldcPhone3	CLDC
9	VgaAGUIPhone1	CDC
10	VgaCdcPhone1	CDC

- Device instances (device definitions). You can make a copy of a device instance, as described in [Section 6.9, "Adding a Device Instance"](#). Go to:

installdir\toolkit-lib\process\device-manager\device-adapter

Profiling Applications

The Java ME SDK supports performance profiling for Java ME applications. The profiler keeps track of every method in your application. For a particular emulation session, it figures out how much time was spent in each method and how many times each method was called.

The SDK supports offline profiling. Data is collected during the emulation session. After you close the emulator you can export the data to a .nps file you can load and view later. As you view the snapshot you can investigate particular methods or classes and save a customized snapshot (a .png file) for future reference.

You can start a profiling session from the NetBeans IDE, as described in [Section 9.1, "Collecting and Saving Profiler Data in the IDE"](#), or from the command line, as discussed in [Section 13.3.4, "Command Line Profiling"](#). It's important to note that profiling data produced from the command line has a different format (*.prof) than data produced from the NetBeans profiler (a .nps file).

The NetBeans IDE has a Profiling window. Because only performance profiling is supported for Java ME, this feature has limited usefulness for Java ME applications.

Note: This feature might slow the execution of your application.

9.1 Collecting and Saving Profiler Data in the IDE


This procedure describes interactive profiling. (To run and profile an application from the command line, see [Section 13.3.4, "Command Line Profiling"](#).)

Note: The profiler maintains a large amount of data, so profiled MIDlets place greater demands on the heap. To increase the Heapsize property. See [Section 6.3, "Setting Device Properties"](#).

1. In the Projects widow, right-click on the project you want to profile and select Profile.
2. If this is the first time profiling this application you are prompted to integrate the profiler with the project. Click OK to perform the integration.



The profiler attaches. You are prompted for the running options.




Choose the CPU Profiler, and optionally check Profile System Classes. Press Run.

3. Start your application.

Interact with the application as you normally would.

4. Exit the MIDlet.

The profile data is automatically displayed in a tab labeled CPU:*time*, where *time* is the time the data was displayed.



5. To export the profile data, press the Export icon and supply a .nps file name and location. This data can be reloaded at a later time. See [Section 9.2, "Loading a .nps File"](#).



6. To save the current view to a .png file, press the "Save current view to image" icon and supply a file name and location.



9.2 Loading a .nps File

A previously exported .nps file ([Section 9.1, "Collecting and Saving Profiler Data in the IDE"](#)) can be loaded at a later time.

Follow these steps to retrieve profile data:

1. Select Profile > Load Snapshot...
2. Choose the .nps file.

The Profiler opens in its own tab labeled CPU:*time*.

Note: The profiling values obtained from the emulator do not reflect actual values on a real device.

Network Monitoring

MIDP applications, at a minimum, are capable of HTTP network connections, but many other types of network connections are also possible. The network monitor provides a convenient way to see the information your application is sending and receiving on the network. This is helpful if you are debugging network interactions or looking for ways to optimize network traffic.

Networking monitoring works for emulators only (it is not supported for real devices).


- [Section 10.1, "Monitor Network Traffic"](#)
- [Section 10.2, "Filter or Sort Messages"](#)
- [Section 10.3, "Save and Load Network Monitor Information"](#)
- [Section 10.4, "Clear the Message Tree"](#)

10.1 Monitor Network Traffic

Follow these steps to activate the network activity for an application.


1. Make the project you want to profile the main project, and from the Profile Menu, choose Profile Main Project. Alternatively, right click on the project in the Projects widow, and select Profile.
2. If this is the first time profiling this application you are prompted to integrate the profile with the main project. Click OK to perform the integration.

In the Profile window, select Network Monitor, and click Run.



3. Start your application.

When the application makes any type of network connection, information about the connection is captured and displayed in the Network Monitor tab.



The top frame displays a list of messages. Click a message to display its details in the bottom frame.

In the Hex View, message bodies are shown as raw hexadecimal values with the equivalent text. To avoid memory issues, the Hex view is currently limited to 16kB of data.

Note: You can examine messages that are still in the process of being sent. Incomplete messages are indicated by bold highlighting in the message tree.

10.2 Filter or Sort Messages

Filters are useful for examining some subset of the total network traffic.

- In the [Select Devices] list check only the devices you want to view.
- In the [Select Protocols] list check only the protocols you want to view. The supported protocols are datagram, socket, http, and https.
- Click the magnifying glass in the Network Monitor toolbar to search for a specific string in the data in the Phone or URL columns.

To arrange the message tree in a particular order, click on the Sort By combo box and choose a criteria.

Time. Messages are sorted in chronological order of time sent or received.

URL. Messages are sorted by URL address. Multiple messages with the same address are sorted by time.

Note: Sorting parameters are dependent on the message protocol you choose. For instance, sorting by time is not relevant for socket messages.

10.3 Save and Load Network Monitor Information

To save your network monitor session, click the blue disk icon at the left of the Network Monitor toolbar.



Choose a file name. The default file extension is .nmd (network monitor data).

To load a network monitor session, choose Profile > Java ME > Load Network Monitor Snapshot... and browse to the .nmd file you saved.

Note: To avoid memory issues, the Hex view display is currently limited to 16kB of data.

10.4 Clear the Message Tree

To remove all messages from the network monitor choose the clear icon (the broom icon on the right of the Network Monitor tool bar).

Lightweight UI Toolkit

The Lightweight UI Toolkit (LWUIT) is a lightweight widget library inspired by Swing but designed for constrained devices such as mobile phones and set-top boxes. Lightweight UI Toolkit supports pluggable theme-ability, a component and container hierarchy, and abstraction of the underlying GUI toolkit. The term lightweight indicates that the widgets in the library draw their state in Java source without native peer rendering.

11.1 LWUIT and the Java ME SDK

LWUIT is an open source project whose source is available at <http://lwuit.java.net>.

Java ME SDK 3.0.5 ships with the LWUIT 1.5 library, which is installed as a NetBeans package. For information on this release, see the product page at:

<http://www.oracle.com/technetwork/java/javame/javamobile/download/lwuit/index.html>

The *Lightweight UI Toolkit Developer's Guide* is available in PDF and HTML formats:

PDF: http://download.oracle.com/javame/dev-tools/lwuit-1.5/LWUIT_Developer_Guide.pdf

HTML:

<http://download.oracle.com/javame/dev-tools/lwuit-1.5/devguide/toc.htm>

As an open source project, LWUIT has an independent release schedule. The Java ME SDK Update Center will update LWUIT when an official binary is released.

It's possible that you might want to use a development version of the LWUIT library. You can add a newer version as described in [Section 11.3, "Add a Different LWUIT Library"](#).

11.2 LWUIT Resource Editor

The Resource Editor is an independent GUI tool for opening, creating, and editing resource packages for LWUIT.

To use the resource editor, select a project that uses the LWUIT library and select Java ME > LWUIT Resource Editor.

The Resource Editor has its own help, and tutorials that are accessed from the Resource Editor's Help menu. These articles link back to the LWUIT blog maintained by Shai Almog. For traditional documentation, see the "Resources" chapter in the Developer's Guide mentioned in [Section 11.1, "LWUIT and the Java ME SDK"](#).

11.3 Add a Different LWUIT Library

The LWUIT library can be added to any CLDC/MIDP or CDC/PBP Project. A library has typically been installed as a NetBeans module.

1. Right-click on a project and select Properties.
2. In the Build category, select Libraries & Resources, and click the Add Library... button.
3. In the Add Libraries window, scroll down and select LWUIT and click Add Library.

You can see the package under Libraries and Resources.

If you have a created a Zip or JAR from the unreleased LWUIT source you can add it in a similar fashion by pressing the Add Jar/Zip button.

11.4 LWUIT Demos

This release provides new and updated demos and sample code. Most of these demos are self-evident user interface samples.

Note: Many LWUIT demos access common internet sites and services through publicly available APIs. To see the demos working as intended you might have to change your proxy settings or create an exception in your antivirus software.

- **LWUITBrowser**

From the menu, select Help for an explanation of this demo.

- **LWUITDemo**

This application has demos for many features. From the Menu choose About for a description of the demo. Choose a subdemo and press the Help soft button for an explanation.

- **LWUITIODemo**

This application implements IO features. For example, type LWUIT in the Search box, choose blog from the Type menu, and press Go. Click the search results to load the page into your system's default browser.

- **LWUITMakeover**

This demo features a search performed by distance, title, rating, or relevance. Search results can be mapped. To "makeover" the demo by choose a different them from the Menu.

- **LWUITSpeed**

This demo tests drawing speed for different components. Press the Start button to cycle through a series of animations. To change the performance you can edit the frame rate in SpeedMIDlet.java. You can also affect the performance by changing the emulator's heap size. In the Device Selector, right-click on the device, select Properties from the context menu, and change the Heapsize value.

- **LWUITTimeZone**

This application shows a contacts list and provides date and time information for contacts displayed on the home page. Use + to add contacts and - to remove them.

Press the sun symbol to toggle the time format between 24 hour time and civilian time.

- **LWUITTipster**

The demo is a simple tip calculator. The default service is restaurant staff. To change the service type, click the up arrow to highlight the service types. Use the right or left arrows to highlight a service type, then click the select button.

Security and MIDlet Signing

The Java ME SDK supports the security policies and domains defined by both JSR 185 (Java Technology for the Wireless Industry or JTWI) and JSR 248 (Mobile Service Architecture or MSA). The SDK provides tools to sign MIDlet suites, manage keys, and manage root certificates. The security domains are further described in [Section 12.1, "Security Domains"](#).

MIDP 2.0 (JSR 118) includes a comprehensive security model based on protection domains. MIDlet suites are installed into a protection domain that determines access to protected functions. The MIDP 2.0 specification also includes a recommended practice for using public key cryptography to verify and authenticate MIDlet suites.

The general process to create a cryptographically signed MIDlet suite is as follows:

1. The MIDlet author, probably a software company, buys a signing key pair from a certificate authority (the CA).
2. The author signs the MIDlet suite with the signing key pair and distributes their certificate with the MIDlet suite.
3. When the MIDlet suite is installed on the emulator or on a device, the implementation verifies the author's certificate using its own copy of the CA's root certificate. Then it uses the author's certificate to verify the signature on the MIDlet suite.
4. After verification, the device or emulator installs the MIDlet suite into the security domain that is associated with the CA's root certificate.

For definitive information, consult the MIDP 2.0 specification. For an overview of MIDlet signing using the Java ME SDK, read the article *Understanding MIDP 2.0's Security Architecture*, which is available at

<http://developers.sun.com/techtopics/mobile/midp/articles/permissions/>.

If you need more background on public key cryptography, try the article *MIDP Application Security 1: Design Concerns and Cryptography*, which is available at <http://developers.sun.com/techtopics/mobile/midp/articles/security1/>. See the following topics:

- [Section 12.1, "Security Domains"](#)
- [Section 12.2, "Setting Security Domains"](#)
- [Section 12.3, "Signing a Project"](#)
- [Section 12.4, "Managing Keystores and Key Pairs"](#)
- [Section 12.5, "Managing Root Certificates"](#)

12.1 Security Domains

The SDK supports five security domains for MSA:

`unidentified_third_party`. Provides a high level of security for applications whose origins and authenticity cannot be determined. The user is prompted frequently when the application attempts a sensitive operation.

`identified_third_party`. Intended for MIDlets whose origins were determined using cryptographic certificates. Permissions are not granted automatically, but the user is prompted less often than for the `unidentified_third_party` domain.

`manufacturer`. Intended for MIDlet suites whose credentials originate from the manufacturer's root certificate.

`minimum`. All permissions are denied to MIDlets in this domain.

`maximum`. All permissions are granted to MIDlets in this domain. Maximum is the default setting.

The SDK includes four JTWI security domains:

`untrusted`. Provides a high level of security for applications whose origins and authenticity cannot be determined. The user is prompted frequently when the application attempts a sensitive operation.

`trusted`. All permissions are granted to MIDlets in this domain.

`minimum`. All permissions are denied to MIDlets in this domain.

`maximum`. All permissions are granted to MIDlets in this domain (equivalent to `trusted`.) Maximum is the default value.

12.2 Setting Security Domains

In the SDK, when you use Run via OTA your packaged MIDlet suite is installed directly into the emulator where it is placed in a security domain. The emulator uses public key cryptography to determine the appropriate security domain.

- If the MIDlet suite is not signed, it is placed in the default security domain.
- If the MIDlet is signed, it is placed in the protection domain that is associated with the root certificate of the signing key's certificate chain. See [Section 12.3, "Signing a Project"](#).

12.2.1 Specify the Security Domain for an Emulator

1. In the Device Selection window, right-click on the device and select Properties.
2. Find the Security Domain setting and make a selection from the context menu.

The SDK knows the runtimes the device can support and supplies only possible domains. The default for both MSA and JTWI is Maximum. See the topic "Setting Device Properties". See [Section 6.3, "Setting Device Properties"](#).

12.2.2 Specify the Security Domain for a Project

1. Right-click on a project and select Properties.
2. In the Category area, select Running (the green triangle).
3. Select Regular Execution and check the Security domain box.

In this context regular execution means you are running in the emulator, as opposed to running OTA.

4. Select the domain from the drop-down menu.

12.3 Signing a Project

Devices use signing information to check an application's source and validity before allowing it to access protected APIs. For test purposes, you can create a signing key pair to sign an application. The keys are as follows:

- A private key that is used to create a digital signature, or certificate.
- A public key that anyone can use to verify the authenticity of the digital signature.

You can create a key pair with the Keystores Manager as described in [Section 12.4, "Managing Keystores and Key Pairs"](#).

12.3.1 Sign a CLDC Project With a Key Pair

1. Right-click on a project and select Properties.
2. From the Build hierarchy, select Signing.
3. Check the Sign Distribution checkbox.
4. Choose a keystore from the Keystores drop-down menu, or click Open Keystores Manager to create a new keystore.

The Certificate Details area displays the Alias, Subject, Issuer, and validity dates for the selected keystore.

5. Choose a key pair alias from the drop-down menu.

A keystore might be accessed by several key pairs, each with a different alias. If you prefer to use a unique key pair, select Open Keystores Manager and create a new key pair. See [Section 12.4.1.1, "Create a Keystore"](#).

6. Click OK.

See [Section 5.4.5, "Obfuscating"](#).

12.3.2 Sign a CDC Project

To sign a CDC project use the JDK jarsigner command from the command line. For example:

```
jarsigner.exe -keystore keystore.ks -storepass keystorepwd MyCdcApp.jar dummyCA
```

12.4 Managing Keystores and Key Pairs

For test purposes, you can create a signing key pair to sign a MIDlet. The Keystores Manager administers this task, as described in the remainder of this topic. The key pair consists of two keys:

- A private key that is used to create a digital signature, or certificate.
- A public key that can be used by anyone to verify the authenticity of the signature.

To deploy on a device, you must obtain a signing key pair from a certificate authority recognized by the device. You can also import keys from an existing Java SE platform keystore.

The following topics describe the user interface:

- [Section 12.1, "Security Domains"](#)
- [Section 12.4.1.3, "Create a New Key Pair"](#)
- [Section 12.4.1.4, "Remove a Key Pair"](#)
- [Section 12.4.1.5, "Import an Existing Key Pair"](#)

You can also use the command line tools described in [Section 13.6, "Command Line Security Features"](#).

12.4.1 Working With Keystores and Key Pairs

The Keystores Manager handles creating and using keystores. The keystores known to the Keystores Manager are listed when you sign a project, as described in [Section 5.4.6, "Signing"](#).

Keystores contain key pairs, which you can also manage from this dialog. You must select a keystore to access the key pair tools.

- [Section 12.1, "Security Domains"](#)
- [Section 12.4.1.3, "Create a New Key Pair"](#)
- [Section 12.4.1.4, "Remove a Key Pair"](#)
- [Section 12.4.1.5, "Import an Existing Key Pair"](#)

12.4.1.1 Create a Keystore

1. Select Tools > Keystores.

The Keystores Manager opens.

2. Click Add Keystore.

The Add Keystores window opens.

3. Choose Create Keystore.

4. Supply a name, location, and password.

`C:\Documents and Settings\user\My Documents`

5. Click OK.

The new keystore appears in the Keystores list.

12.4.1.2 Add an Existing Keystore

1. Select Tools > Keystores.

The Keystores Manager opens.

2. Click Add Keystore.

The Add Keystores window opens.

3. Choose Add Existing Keystore.

4. Browse to the location of the keystore and select the keystore file. Click OK.

`C:\Documents and Settings\user\My Documents`

5. Click OK.

The new keystore appears in the Keystores list.

12.4.1.3 Create a New Key Pair

1. Select Tools > Keystores.

The Keystores Manager opens.

2. Select a Keystore in the Keystores area on the left.

If you prefer a different keystore, select Add Keystore to create a new keystore or add an existing keystore.

3. Click the New button.

4. Fill in the Create Key Pair dialog.

You must provide an alias to refer to this key pair.

The six Certificate Details fields are provisionally optional. You must complete at least one field.

Key Pair Alias. The name used to refer to this key pair.

Common Name. Common name of a person, such as "Jane Smith"

Organization Unit. Department or division name, such as "Development"

Organization Name. Large organization name, such as "Sun Microsystems Inc."

Locality Name. Locality (city) name, such as "Santa Clara"

State Name. State or province name, such as "California"

Country. Two-letter country code, such as "US"

The password is optional. If you do provide a password, it must have at least six characters.

5. Click OK.

The new key is displayed in the Keys area under its alias. You can now select this keypair when you sign a project. See [Section 12.3, "Signing a Project"](#).

12.4.1.4 Remove a Key Pair

1. Select Tools > Keystores.
2. In the Keys area, click on a Key Pair.
3. Select Delete.

12.4.1.5 Import an Existing Key Pair

If you have keys in a Java SE platform keystore that you would like to use for MIDlet signing, you can import the signing keys to the Java ME SDK.

1. Select Tools > Keystores.
2. Click Add Keystores.

The Add Keystores window opens.

3. Click Add Existing Keystore.
4. Browse to the keystore location.
5. Click OK.

12.5 Managing Root Certificates

The Java ME SDK command line tools described in [Section 13.6.3, "Manage Certificates \(MEKeyTool\)"](#) manage the emulator's list of root certificates.

Real devices have similar lists of root certificates, although you typically cannot modify them. When you deploy your application on a real device, you must use signing keys issued by a certificate authority whose root certificate is present on the device. This makes it possible for the device to verify your application.

Each emulator instance has its own `_main.ks` file located in its `appdb` directory. For example: `userhome\javame-sdk\3.0.5\work\emulator-instance-id\appdb`.

The micro keystore, `_main.ks` resides in the following directory:

`installdir\runtimes\cldc-hi\appdb\`

The default keystore `keystore.ks` resides in `installdir\runtimes\cldc-hi\lib`.

You can use the `-import` option to import certificates from these keystores as described in [Section 13.6.3, "Manage Certificates \(MEKeyTool\)"](#).

Command Line Reference

This topic describes how to operate the Java ME SDK from the command line and details the command line tools required to build and run an application.

- [Section 13.1, "Run the Device Manager"](#)
- [Section 13.2, "Manage Device Addresses \(device-address\)"](#)
- [Section 13.3, "Emulator Command Line Options"](#)
- [Section 13.4, "Build a Project from the Command Line"](#)
- [Section 13.5, "Packaging a MIDLet Suite \(JAR and JAD\)"](#)
- [Section 13.6, "Command Line Security Features"](#)
- [Section 13.7, "Generate Stubs \(wscompile\)"](#)

13.1 Run the Device Manager

The device manager is a component that runs as a service. It detects devices (real or emulated) that conform\ to the Universal Emulator Interface Specification (http://java.sun.com/j2me/docs/uei_specs.pdf), version 1.0.2. The Device Manager automatically restarts every time you use the SDK. You can manually launch the device manager from a script or a command line.

installdir\bin\device-manager.exe

To see a log of activities, launch the device manager with the `-XenableOutput` option.

13.2 Manage Device Addresses (device-address)

installdir\bin\device-address is a tool for viewing, adding, and removing devices that the SDK is not able to discover automatically. The Microsoft device emulator is an example of such a device. The syntax is:

Table 13-1 Device Address Commands

Command	Action
<code>add address_type address</code>	Add the specified address.
<code>del address_type address</code>	Delete the specified address.
<code>list</code>	List all address types.
<code>list address_type</code>	List the specified address type.

For example, the following command adds a device:

```
installdir\bin\device-address.exe add ip 192.168.1.2
```

13.3 Emulator Command Line Options

You can launch the emulator independent of the GUI using `bin\emulator`. The syntax is as follows:

```
emulator options
```

The general options are as follows:

Table 13–2 Emulator Commands

Command	Action
<code>-classpath path</code>	Specifies a search path for application classes. The path consists of directories, ZIP files, and JAR files separated by colons.
<code>-cp path</code>	
<code>-Dproperty=value</code>	Sets a system property value.
<code>-help</code>	Display a list of valid options.
<code>-version</code>	Display version information about the emulator.
<code>-Xdevice:instance-name</code>	Run an application on the emulator using the given device instance name.
<code>-Xquery</code>	Print emulator skin information on the standard output stream and exit immediately. The information includes the skin name, screen size, and other capabilities.

This is a simple example of running the emulator from the command line:

```
emulator.exe -Xdescriptor:C:\Java_ME_platform_SDK_3.0.5\apps\Games\dist\Games.jad
```

`emulator.exe` also supports [Section 13.3.1, "MIDlet Options"](#), [Section 13.3.2, "CDC Options"](#), and [Section 13.3.3, "Debugging and Tracing Options"](#).

13.3.1 MIDlet Options

Options for running MIDlets in the emulator are as follows:

- `-Xautotest:JAD-file-URL`

Run in autotest mode. This option installs a MIDlet suite from a URL, runs it, removes it, and repeats the process. The purpose is to run test compatibility kits (TCKs) with the emulator, using a test harness such as JT Harness (<http://jtharness.java.net>), or Java Device Test Suite (JDTs) (<http://java.sun.com/products/javadevice/overview.html>). For example:

```
emulator -Xautotest:http://localhost:8080/test/getNextApp.jad
```

Given the above command, `-Xautotest` causes the emulator to repeatedly install, run, and remove the first MIDlet from the MIDlet suite provided through the HTTP URL. Once the emulator starts, it queries the test harness, which then downloads and installs the TCK MIDletAgent.

- `-Xdescriptor:jad-file`

Install a MIDlet, run it, and uninstall it after it finishes.

- `-Xdomain:domain-name`

Set the MIDlet suite's security domain.

The `-Xjam` argument runs an application remotely using the Application Management Software (AMS) to run OTA provisioning. If no application is specified with the argument, the graphical AMS is run.

- `-Xjam[::<JAD-file-url> | force|list|storageNames|run=[<storageNames>|<StorageNumber>]|remove=[<storage name>|<storage number> | all]]`
 - Installs the application with the specified JAD file onto a device.
 - `force`. If an existing application has the same storage name as the application to be installed, `force` removes the existing application before installing the new application.
 - `list`. List all the applications installed on the device and exit. The list is written to standard output before the emulator exits.
 - `storageNames`. List all applications installed on the device. The list is written to standard output before the emulator exits. Each line contains one storage name in numerical order. The list contains only the name so the order is important. For example the first storage name must be storage number 1.
- `-Xjam:run=[<storage-name> | <storage-number>]`
 - Run a previously installed application. The application is specified by its valid storage name or storage number.
- `-Xjam:remove=[<storage-name> | <storage-number> | all]`
 - Remove a previously installed application. The application is identified by its valid storage name or storage number. If `all` is supplied, all previously installed applications are removed.
- `transient=jad-file-url`
 - If specified, `transient` is an alias for installing, running, and removing the application with the specified JAD file.

This example illustrates OTA installation:

```
emulator -Xjam:install=http://www.myserver.com/apps/MyApp.jad
-Xdevice:DefaultCldcMsaPhone2
```

The above command returns the ID of the installed application. Once you obtain the ID you can run it with: `emulator=Xjam:run=ID`

See also [Section 13.3, "Emulator Command Line Options"](#) and [Section 13.3.3, "Debugging and Tracing Options"](#).

13.3.2 CDC Options

The following options apply to CDC projects.

- `-Xmain:main-class-name`
 - Run the main method of a Java class, as in Java SE.
- `-Xxlet:classpath=class-path, class=fully-qualified-name, [arg=argument]*`
 - Run an Xlet application.

See also [Section 13.3, "Emulator Command Line Options"](#) and [Section 13.3.3, "Debugging and Tracing Options"](#).

13.3.3 Debugging and Tracing Options

You can use the following options with the emulator for debugging and tracing CLDC projects.

- `-Xdebug`

Enable runtime debugging. The `-Xrunjdwp` option must be called to support `-Xdebug`.

- `-Xrunjdwp:debug-settings`

Start a Java debug wire protocol session, as specified by a list of comma-separated debug settings. Both `-Xrunjdwp` and `-Xdebug` must be called.

Valid debug settings include the following:

- `transport=transport-mechanism` - Transport mechanism used to communicate with the debugger. The only transport mechanism supported is `dt_socket`.
- `address=host:port` - Transport address for the debugger connection. If `host` is omitted, `localhost` is assumed to be the host machine.
- `server={y|n}` - Starts the debug agent as a server. The debugger must connect to the port specified. The possible values are `y` and `n`. Currently, only `y` is supported (the emulator must act as a server).
- `suspend={y|n}` - The possible values are `y` and `n`.

When `suspend` is set to `n`, the application starts immediately and the debugger can be attached at any time during its run.

When `suspend` is set to `y`, the application does not start until a debugger attaches to the debugging port and sends a resume command. This means that an application can be debugged from the very beginning.

This example shows debugging:

```
emulator.exe -Xdevice:DefaultClcdPhone2 -Xdebug -Xrunjdwp:transport=dt_socket,suspend=n,  
server=y,address=51307 -Xdescriptor:..\apps\Games\dist\Games.jad -Xdomain:maximum
```

With the emulator running you can attach a debugger.

- To attach a graphical debugger from NetBeans, select Debug > Attach Debugger.
- To attach a command line debugger, see:
<http://download.oracle.com/javase/6/docs/technotes/tools/windows/jdb.html>

A sample command would be:

```
jdb -connect com.sun.jdi.SocketAttach:hostname=localhost,port=51307
```

13.3.4 Command Line Profiling

To add profiling to an emulator session, use:

```
-Xprofile:file=filename.prof
```

For example:

```
emulator.exe -Xdevice:DefaultClcdPhone1 -Xprofile:file=D:\Temp\Games.prof  
-Xdescriptor:..\apps\Games\dist\Games.jad
```

When you launch the emulator and profile an application from the command line the data profile you save has a different format than .nps files created with the Profile option in the NetBeans IDE.

Files created from the command line should be given the extension .prof to distinguish them from IDE profiler files.

To view .prof files in the IDE, select Profile > Java ME > Import CPU Profiler Snapshot. Your file is displayed in a tab labeled with the time the snapshot was taken.

Once the file is loaded in the IDE you can export the data in .nps form, using the Export to... feature as described in [Section 9.1, "Collecting and Saving Profiler Data in the IDE"](#), step 5. These files can be loaded using Profile > Java ME > Load Snapshot...

13.4 Build a Project from the Command Line

In the user interface, building a project is a single step. Behind the scenes, however, there are two steps. First, Java source files are compiled into Java class files. Next, the class files are *preverified*, which means they are prepared for the CLDC VM. See the following topics:

- [Section 13.4.1, "Check Prerequisites"](#)
- [Section 13.4.2, "Compile Class Files"](#)
- [Section 13.4.3, "Preverify Class Files"](#)

13.4.1 Check Prerequisites

Before building and running an application from the command line, verify that you have a version no earlier than 1.5 of the Java SE software development kit. Make sure the `jar` command is in your path. To find the version of the development kit, run `java -version` at the command line.

13.4.2 Compile Class Files

Use the `javac` compiler from the Java SE development kit to compile Java source files. You can use the existing Java ME SDK project directory structure. Use the `-bootclasspath` option to tell the compiler to use the MIDP APIs, and use the `-d` option to tell the compiler where to put the compiled class files.

The following example demonstrates how you might compile a MIDP 2.0 application, taking source files from the `src` directory and placing the class files in the `tmpclasses` directory. Newlines have been added for clarity.

```
javac -target 1.3 -source 1.3
      -bootclasspath ..\..\lib\cldc_10.jar;..\..\lib\midp2.0.jar
      -d tmpclasses
      src\*.java
```

For more information on `javac`, consult the Java SE documentation.

13.4.3 Preverify Class Files

The next step is to preverify the class files. The `bin` directory of the Java ME SDK includes the `preverify` utility. The syntax for the `preverify` command is as follows:

```
preverify files | directories
Some of the options are as follows:
```

<code>-classpath <i>classpath</i></code>	Specify the directories or JAR files (given as a semicolon-delimited list) from which classes are loaded.
<code>-d <i>output-directory</i></code>	Specify the target directory for the output classes. This directory must exist before preverifying. If this option is not used, the preverifier places the classes in a directory called <code>output</code> .

Following the example for compiling, use the following command to verify the compiled class files. As before, newlines are added for clarity.

```
preverify.exe
  -classpath ..\..\lib\cldcapi10.jar;..\..\lib\midpapi20.jar
  -d classes
  tmpclasses
```

As a result of this command, preverified class files are placed in the `classes` directory. If your application uses WMA, MMAPI, or other versions of CLDC or MIDP, be sure to include the relevant `.jar` files in the classpath.

13.5 Packaging a MIDlet Suite (JAR and JAD)

To package a MIDlet suite manually you must create a manifest file, an application JAR file, and finally, a MIDlet descriptor (also known as a Java Application Descriptor or JAD).

Create a manifest file containing the appropriate attributes as specified in the MIDP specification. You can use any text editor to create the manifest file. For example, a manifest might have the following contents:

```
MIDlet-1: My MIDlet, MyMIDlet.png, MyMIDlet
MIDlet-Name: MyMIDlet
MIDlet-Vendor: My Organization
MIDlet-Version: 1.0
MicroEdition-Configuration: CLDC-1.1
MicroEdition-Profile: MIDP-2.1
```

Create a JAR file containing the manifest as well as the suite's class and resource files. To create the JAR file, use the `jar` tool that comes with the Java SE software development kit. The syntax is as follows:

```
jar cfm file manifest -C class-directory . -C resource-directory .
```

The arguments are as follows:

- *file* - JAR file to create.
- *manifest* - Manifest file for the MIDlets.
- *class-directory* - Directory containing the application's classes.
- *resource-directory* - Directory containing the application's resources.

For example, to create a JAR file named `MyApp.jar` whose classes are in the `classes` directory and resources are in the `res` directory, use the following command:

```
jar cfm MyApp.jar MANIFEST.MF -C classes . -C res .
```

Create a JAD file containing the appropriate attributes as specified in the MIDP specification. You can use any text editor to create the JAD file. This file must have the extension `.jad`.

Note: You must set the `MIDlet-Jar-Size` entry to the size of the JAR file created in the previous step.

For example, a JAD file might have the following contents:

```
MIDlet-Name: MyMIDlet
MIDlet-Vendor: My Organization
MIDlet-Version: 1.0
MIDlet-Jar-URL: MyApp.jar
MIDlet-Jar-Size: 24601
```

13.6 Command Line Security Features

The full spectrum of the Java ME SDK's security features are also available from the command line. You can adjust the emulator's default protection domain, sign MIDlet suites, and manage certificates.

- [Section 13.6.1, "Change the Default Protection Domain"](#)
- [Section 13.6.2, "Sign MIDlet Suites \(jadtool\)"](#)
- [Section 13.6.3, "Manage Certificates \(MEKeyTool\)"](#)

13.6.1 Change the Default Protection Domain

To adjust the emulator's default protection domain, use the following option with the emulator command:

`-Xdomain:domain-type`

Assigns a security domain to the MIDlet suite. Enter an appropriate security domain as described in [Section 12.1, "Security Domains"](#). For example, `-Xdomain:maximum`.

13.6.2 Sign MIDlet Suites (jadtool)

`jadtool` is a command-line interface for signing MIDlet suites using public key cryptography according to the MIDP 2.0 specification. Signing a MIDlet suite is the process of adding the signer certificates and the digital signature of the JAR file to a JAD file. `jadtool` is also capable of signing payment update (JPP) files.

`jadtool` only uses certificates and keys from Java SE platform keystores. Java SE software provides `keytool`, the command-line tool to manage Java SE platform keystores.

`jadtool` is packaged in a JAR file. To run it, open a command prompt, change the current directory to `installdir\bin`, and enter the following command:

`jadtool command`

The commands are as follows:

- `-help`
Prints the usage instructions for `jadtool`.
- `-addcert -alias alias [-keystore keystore] [-storepass password] [-storetype PKCS11] [-certnum number] [-chainnum number] [-encoding encoding]`
`-inputjad | inputjpp input-file -outputjad | outputjpp output-file`

Adds the certificate of the key pair from the given keystore to the JAD file or JPP file.

- `-addjarsig [-jarfile <filename>] -keypass <password> -alias <key alias> -storepass <password> [-keystore <none|keystore>] [-storetype <PKCS11>] [-encoding <encoding>] -inputjad <filename> -outputjad <filename>`

Adds the digital signature of the given JAR file to the specified JAD file. The default value for `-jarfile` is the `MIDlet-Jar-URL` property in the JAD file.

- `-showcert [([-certnum <number>] [-chainnum <number>]) | [-all]] [-encoding <encoding>] -inputjad <filename> | -inputjpp <filename>`

Displays information about certificates in JAD and JPP files.

- `-addjppsig -keypass <password> -alias <key alias> [-storepass <password>] [-keystore <none|keystore>] [-storetype <PKCS11>] [-encoding <encoding>] -inputjpp <filename> -outputjpp <filename>`

Adds a digital signature of the input JPP file to the specified output JPP file.

The default values are as follows:

- `-encoding` - `UTF-8`
- `-jarfile` - `MIDlet-Jar-URL` property in the JAD file
- `-keystore` - `$HOME\.keystore`
- `-certnum` - `1`
- `-chainnum` - `1`

13.6.3 Manage Certificates (MEKeyTool)

MEKeyTool manages the public keys of certificate authorities (CAs), making it functionally similar to the keytool utility that comes with the Java SE SDK. The keys can be used to facilitate secure HTTP communication over SSL (HTTPS).

Before using MEKeyTool, you must first have access to a Java Cryptography Extension keystore. You can create one using the Java SE keytool utility (found in the `\bin` directory for your JDK). See:

<http://java.sun.com/javase/6/docs/technotes/tools/windows/keytool.html>

To run MEKeyTool, open a command prompt, change the current directory to `installdir\bin`, and enter the following command:

`installdir\bin\mekeytool.exe -command`

The command keywords follow.

The Java ME SDK contains a default ME keystore named `_main.ks`, which is located in:

`installdir\runtimes\cldc-hi\appdb`

This keystore includes all the certificates that exist in the default Java SE platform keystore that comes with the Java SE installation.

Also, each emulator instance has its own `_main.ks` file located in `userhome\javame-sdk\3.0.5\work\emulator-instance-id\appdb`. If you do not specify a value for `MEkeystore`, a new key is added to the default ME key for this emulator instance.

If you do not specify a value for `-keystore`, the default keystore is used:

```
C:\Documents and Settings\user\.keystore.ks
```

- **-help**
Prints the usage instructions for MEKeyTool.
- **-import -alias alias [-keystore JCEkeystore] [-MEkeystore filename] [-storepass storepass] -domain domain-name**
Imports a public key into the ME keystore from the given JCE keystore using the given Java Cryptography Extension keystore password. and the default Java Cryptography Extension keystore is *userhome\.keystore*.
- **-list [-MEkeystore filename]**
Lists the keys in the ME keystore, including the owner and validity period for each.
- **-delete (-owner owner | -number key-number) [-MEkeystore filename]**
Deletes a key from the given ME keystore with the given owner.

13.7 Generate Stubs (wscompile)

Mobile clients can use the Stub Generator to access web services. The wscompile tool generates stubs, ties, serializers, and WSDL files used in Java API for XML (JAX) RPC clients and services. The tool reads a configuration file, that specifies either a WSDL file, a model file, or a compiled service endpoint interface. The syntax for the stub generator command is as follows:

```
wscompile [options] configuration-files
```

[Table 13-3](#) lists the wscompile options:

Table 13-3 wscompile Options

Option	Description
-d <i>output directory</i>	Specifies where to place generated output files
-f :<i>features</i>	Enables the given features
-features:<i>features</i>	Same as -f :<i>features</i>
-g	Generates debugging info
-gen	Same as -gen:client
-gen:client	Generates client artifacts (stubs, etc.)
-httpproxy:<i>host:port</i>	Specifies a HTTP proxy server (port defaults to 8080)
-import	Generates interfaces and value types only
-model <i>file</i>	Writes the internal model to the given file
-O	Optimizes generated code
-s <i>directory</i>	Specifies where to place generated source files
-verbose	Outputs messages about what the compiler is doing
-version	Prints version information
-cldc1.0	Sets the CLDC version to 1.0 (default). Float and double become String.
-cldc1.1	Sets the CLDC version to 1.1 (float and double are OK)
-cldc1.0info	Shows all CLDC 1.0 information and warning messages.

Note: Exactly one `-gen` option must be specified. The `-f` option requires a comma-separated list of features.

Table 13–4 lists the features (delimited by commas) that can follow the `-f` option. The `wscompile` tool reads a WSDL file, compiled service endpoint interface (SEI), or model file as input. The Type of File column indicates which of these files can be used with a particular feature.

Table 13–4 Command Supported Features (`-f`) for `wscompile`

Option	Description	Type of File
<code>explicitcontext</code>	Turns on explicit service context mapping	WSDL
<code>nodatabinding</code>	Turns off data binding for literal encoding	WSDL
<code>noencodedtypes</code>	Turns off encoding type information	WSDL, SEI, model
<code>nomultirefs</code>	Turns off support for multiple references	WSDL, SEI, model
<code>novalidation</code>	Turns off full validation of imported WSDL documents	WSDL
<code>searchschema</code>	Searches schema aggressively for subtypes	WSDL
<code>serializeinterfaces</code>	Turns on direct serialization of interface types	WSDL, SEI, model
<code>wsi</code>	Enables WSI-Basic Profile features (default)	WSDL
<code>resolveyidref</code>	Resolves <code>xsd:IDREF</code>	WSDL
<code>nounwrap</code>	No unwrap.	WSDL

Examples

```
wscompile -gen -d generated config.xml
wscompile -gen -f:nounwrap -O -cldc1.1 -d generated config.xml
```

14

Logs

Java ME SDK uses the log4j logging facility to manage Device Manager and Device Instance logs.

14.1 Device Manager Logs

The device manager log is placed into:

C:\Documents and Settings\user\javame-sdk\version\log

Logging levels can be configured in the following XML file:

installdir\toolkit-lib\process\device-manager\conf\log4j.xml

A priority value for the categories com.sun or VM can be set to the following levels: ERROR, WARN, INFO, DEBUG, TRACE (ordered from least to most verbose).

```
<category name="com.sun">
  <priority value="DEBUG"/>
  <appender-ref ref="CONSOLE-ALL"/>
  <appender-ref ref="FILE"/>
</category>

<category name="VM">
  <priority value="INFO"/>
  <appender-ref ref="CONSOLE-ALL"/>
  <appender-ref ref="FILE"/>
</category>
```

14.2 Device Instance Logs

Each device (or emulator) instance writes its own log into its directory. See [Table 8-1](#) to correlate the directory number and the device name.

C:\Documents and Settings\user\javame-sdk\version\work\device-#\device.log

The verbosity of the device instance log is controlled by the `log4j.xml` file, as described in [Section 14.1, "Device Manager Logs"](#).

A priority value for the categories com.sun or VM can be set to the following levels: ERROR, WARN, INFO, DEBUG, TRACE (ordered from least to most verbose). The verbosity of the device instance log is controlled by `log4j.xml`.

15

JSR Support

The Java ME SDK supports many standard Application Programming Interfaces (APIs) defined through the Java Community Process (JCP) program. JCP APIs are often referred to as JSRs, named after the Java Specification Request process.

See [Table 15–1](#) for a full list of supported APIs. The Java ME SDK provides documentation describing how certain APIs are implemented in the SDK. Many supported APIs do not require special implementation considerations, so they are not discussed in this help set.

The CLDC/MIDP platform is based on the *Mobile Information Device Profile and Connected Limited Device Configuration* (JSRs 118 and 139).

JSRs that are not part of the platform are referred to as "optional packages." All optional packages are supported on the CLDC/MIDP Platform on Windows.

15.1 JCP APIs

Table 15–1 Supported JCP APIs

JSR, API	Name, URL
JSR 75, PIM and File	<i>PDA Optional Packages for the J2ME Platform</i> http://jcp.org/en/jsr/detail?id=75
JSR 82, Bluetooth and OBEX	<i>Java APIs for Bluetooth</i> http://jcp.org/en/jsr/detail?id=82
JSR 118, MIDP 2.0	<i>Mobile Information Device Profile</i> http://jcp.org/en/jsr/detail?id=118
JSR 135, MMAPI 1.1	<i>Mobile Media API</i> http://jcp.org/en/jsr/detail?id=135
JSR 139, CLDC 1.1	<i>Connected Limited Device Configuration</i> http://jcp.org/en/jsr/detail?id=139
JSR 172, Web Services	<i>J2ME Web Services Specification</i> http://jcp.org/en/jsr/detail?id=172
JSR 177, SATSA	<i>Security and Trust Services API for Java ME</i> http://jcp.org/en/jsr/detail?id=177
JSR 179, Location	<i>Location API for Java ME</i> http://jcp.org/en/jsr/detail?id=179

Table 15–1 (Cont.) Supported JCP APIs

JSR, API	Name, URL
JSR 180, SIP	<i>SIP API for Java ME</i> http://jcp.org/en/jsr/detail?id=180
JSR 184, 3D Graphics	<i>Mobile 3D Graphics API for J2ME</i> http://jcp.org/en/jsr/detail?id=184
JSR 185, JTWI 1.0	<i>Java Technology for the Wireless Industry</i> http://jcp.org/en/jsr/detail?id=185
JSR 205, WMA 2.0	<i>Wireless Messaging API</i> http://jcp.org/en/jsr/detail?id=205
JSR 209, AGUI 1.0	<i>Advanced Graphics and User Interface Optional Package for the J2ME Platform</i> http://www.jcp.org/en/jsr/detail?id=209
JSR 211, CHAPI	<i>Content Handler API</i> http://jcp.org/en/jsr/detail?id=211
JSR 217, PBP 1.1	<i>Personal Basis Profile 1.1</i> http://www.jcp.org/en/jsr/detail?id=217
JSR 218, CDC	<i>Connected Device Configuration</i> http://jcp.org/en/jsr/detail?id=218
JSR 226, SVG	<i>Scalable 2D Vector Graphics API for J2ME</i> http://jcp.org/en/jsr/detail?id=226
JSR 229, Payment	<i>Payment API</i> http://jcp.org/en/jsr/detail?id=229
JSR 234, AMMS	<i>Advanced Multimedia Supplements</i> http://jcp.org/en/jsr/detail?id=234
JSR 238, MIA	<i>Mobile Internationalization API</i> http://jcp.org/en/jsr/detail?id=238
JSR 239	<i>Java Binding for OpenGL ES API</i> http://jcp.org/en/jsr/detail?id=239
JSR 248, MSA 1.0	<i>Mobile Service Architecture</i> http://jcp.org/en/jsr/detail?id=248
JSR 253, MTA	<i>Mobile Telephony API (MTA)</i> http://jcp.org/en/jsr/detail?id=253
JSR 256	<i>Mobile Sensor API</i> http://jcp.org/en/jsr/detail?id=256
JSR 257	<i>Contactless Communication API</i> http://jcp.org/en/jsr/detail?id=257
JSR 258	<i>Mobile User Interface Customization API</i> http://jcp.org/en/jsr/detail?id=258
JSR 280, XML API	<i>XML API for Java ME</i> http://jcp.org/en/jsr/detail?id=280

Table 15–1 (Cont.) Supported JCP APIs

JSR, API	Name, URL
JSR 293, Location	<i>Location API 2.0</i> http://jcp.org/en/jsr/detail?id=293

16

JSR 75: PDA Optional Packages

The Java ME SDK supports JSR 75, the PDA Optional Packages (PDAP) for the J2ME Platform. JSR 75 includes two independent APIs:

- The `FileConnection` optional package allows MIDlets access to a local device file system.
- The Personal Information Management (PIM) optional package includes APIs for manipulating contact lists (address book), calendars, and to-do lists.

This chapter describes how the Java ME SDK implements the `FileConnection` and PIM APIs.

16.1 FileConnection API

On a real device, the `FileConnection` API typically provides access to files stored in the device's memory or on a memory card.

In the Java ME SDK emulator, the `FileConnection` API enables MIDlets to access files stored on your computer's hard disk.

The files that can be accessed using the `FileConnection` optional package are stored in the following subdirectory:

`Documents and Settings\user\javame-sdk\3.0.5\work\emulator-instance\appdb\filesystem`

For example, the `DefaultCldcPhone1` emulator instance comes with a root directory installed called `root1`, which contains a `Readme` file and an empty directory named `photos`.

Each subdirectory of `filesystem` is called a *root*. The Java ME SDK provides a mechanism for managing roots. While the emulator is running, choose Device > File Connection. This opens with the File Connection tab selected.

In the File Connection panel you can mount, unmount, or delete filesystem roots. Mounted roots are displayed in the top list, and unmounted roots are moved to the bottom list. Mounted root directories and their subdirectories are available to applications using the `FileConnection` API. Unmounted roots can be remounted in the future.

- To add a new empty filesystem root directory, click Mount Empty and fill in a name for the directory.
- To mount a copy of an existing directory, click Mount Copy, and browse to choose a directory you want to copy. When the File System Root Entry dialog opens, enter the name for this root. A deep copy of the selected directory is placed into the emulator's filesystem with the specified root name.

- To make a directory inaccessible to the FileConnection API, select it in the list and click Unmount. The selected root is unmounted and moved to the Unmounted roots list.
- To completely remove a mounted directory, select it and click Unmount & Delete.
- To remount an unmounted directory, select it and click Remount. The root is moved to the mounted roots list.
- To delete an unmounted directory, select it and click Delete. The selected root is removed from the list.

16.2 PIM API

The Java ME SDK emulator stores contact, calendar, and to-do information in standard files on your desktop computer's hard disk. All information is stored in:

Documents and Settings\user\javame-sdk\3.0.5\work\emulator-instance\appdb\PIM

Each device instance has its own data. Lists are stored in subdirectories of the contacts, events, and todo directories. For example, a contact list called Contacts is contained in \appdb\PIM\Contacts:

Inside the list directory, items are stored in vCard (.vcs) or vCalendar (.vcf) format (see <http://www.imc.org/pdi/>). Contacts are stored in vCard format, while calendar and to-do items are both stored in vCalendar format.

16.3 Running PDAPDemo

PDAPDemo shows how to use the PIM and FileConnection APIs that are part of the JSR 75 specification.

16.3.1 Browsing Files

To run the file browser, you'll need to give the MIDlet appropriate security authorization, if you have not already done so. Right-click on your project, choose Properties, and select Specify the Security Domain. If necessary, select the maximum domain and press OK.


Now open and run the PDAPDemo project. Launch the FileBrowser MIDlet. You see a directory listing, and you can browse through the available directories and files. By default there is one directory, root1. This directory is located at:

Documents and Settings\user\javame-sdk\version\work\instance\appdb\filesystem\root1



Select the directory and press the View soft button to enter it.

The directories `photos` and `private` are empty by default. You can add files and root directories and they will be visible to the JSR 75 File API. (This demo shows a `README` and some JPEGs that were added to the local `photos` directory.)




Using the Menu commands you can view a file or see its properties. Try selecting the file and choosing Properties or View from the menu.

16.3.2 The PIM API


The JSR75 PIM APIs example demonstrates how to access personal information, like contact lists, calendars, and to-do lists. After you launch the example, choose a type of list from the main menu.

In this example application, each type of list works the same way and each list type contains a single list. For example, if you choose Contact Lists, there is a single contact list called Contacts. Event Lists contains a single list called Events, and To Do Lists contains a single list named To Do.



Once you've selected a list type and chosen the specific list, you can view all the items in the list. If this is the first time you've run the example, the list is probably empty.

To add an item, choose New from the menu. The application prompts you for a Formatted Name for the item. You can add more data fields to this item using option 3, Add Field, in the menu. You see a list of field names. Pick as many as you like. You can fill in the field at any time.



To save the list item, choose Commit (option 5) from the menu.

To return to the list, choose the Back command. You'll see the item you just created in the list.

The items that you create are stored in standard vCard or vCalendar format in the *device\pim* directory.

The PIM API allows for exporting contact, calendar, and to-do items in a standard format. The exact format depends on the list type. When you are viewing an item in any list, the menu contains a command for viewing the exported item.

For example, when you are viewing a contact list item, the menu contains Show vCard. When you choose this command, the exported item is shown on the screen. Calendar items and to-do items both get exported as vCalendar.

JSR 82: Bluetooth and OBEX Support

The Java ME SDK emulator supports JSR 82, the Java APIs for Bluetooth. The emulator is fully compliant with version 1.1 of the specification, which describes integration with the push registry. JSR 82 includes two independent APIs:

- The Bluetooth API provides an interface to Bluetooth wireless networking, including device discovery and data exchange.

The Java ME SDK emulator enables you to develop and test applications that use Bluetooth without having actual Bluetooth hardware. The SDK simulates a Bluetooth environment for running emulators. Multiple emulator instances can discover each other and exchange data using the Bluetooth API.

For an example, see [Section 17.2, "Running the Bluetooth Demo"](#).

- The OBEX API allows applications to use the Object Exchange (OBEX) protocol over Bluetooth or other communication channels.

The Java ME SDK implements OBEX transfer over simulated Bluetooth and TCP connections.

For an example, see [Section 17.3, "Running the OBEX Demo"](#).

This chapter describes how the Java ME SDK implements the Bluetooth and OBEX APIs.

17.1 Setting OBEX and Bluetooth Properties

The Java ME SDK enables you to configure the Bluetooth and OBEX simulation environment. Because the simulation requires a sender and receiver, Bluetooth settings are configured separately for each device. Follow these steps to set device properties.

1. In the device selector right-click on a CLDC device.

The device properties are displayed in the Properties window. If you don't see this window, select Window > Properties from the NetBeans toolbar.

2. Scroll down to see the Bluetooth and OBEX properties. When you click a property a description is shown in the description area. If you can't see this area, right click a property and select Show Description Area.

The System Properties can be retrieved in an application using the `getProperty()` method in `javax.bluetooth.LocalDevice`. The Bluetooth properties are fully described in the JSR 82 specification.

- **bluetooth.sd.trans.max**

The maximum number of concurrent service discovery transactions.

The default is 8.

- **bluetooth.sd.attr.retrieveable.max**
The maximum number of service attributes to be retrieved per service record.
- **bluetooth.master.switch**
Enable/disable a master/slave switch.
- **bluetooth.l2cap.receiveMTU.max**
The maximum ReceiveMTU size in bytes supported in L2CAP. This is the maximum payload size this connection can accept.
The default value is 672.
- **OBEX Maximum Packet Length**
The default is 4096 bytes.
The maximum packet length affects how much data is sent in each packet between emulators. Shorter packet values result in more packets and more packet overhead.
- **IrDA OBEX Discovery Timeout**
The default is 10000 milliseconds.
Devices using IrDA in the real world discover other devices by listening. At the API level, the discovery timeout value determines how long a call to `Connector.open("irdaobex://discover...")` blocks before it returns or throws an exception.

17.2 Running the Bluetooth Demo

This application contains MIDlets that demonstrate the use of JSR 82's Bluetooth API. It shows how images can be transferred between devices using Bluetooth.

You must run two emulator instances to see this process, and each device must have a different phone number.

1. Use DefaultCldcPhone1 to launch Bluetooth Demo, then launch Bluetooth Demo on DefaultCldcPhone2.
2. The demo gives you a choice of Server or Client.
3. On the first emulator, highlight Server and use the left softbutton to choose OK.

The server starts and displays a list of images. At the beginning, none of the images are available on the Bluetooth network.

Select the image you want to make available.

Press Publish image (the left soft button). The icon color changes from purple to green, indicating it is published.

4. On the second emulator running the Bluetooth Demo, highlight Client and choose OK. The MIDlet displays "Ready for images search". Click the Find soft button. The MIDlet finds the other emulator and gets a list of published images. Select one from the list and choose Load.

- If you are running the demonstration in a trusted protection domain, the image is transferred using simulated Bluetooth and is shown on the client emulator.

- If you are not running in a trusted protection domain, the first emulator (the server) displays a prompt asking if you want to authorize the connection from the client. Choose Yes. The image is displayed in the client emulator.

17.3 Running the OBEX Demo

This application shows how to transfer image files between emulator instances using the OBEX API. This demonstration shows the use of OBEX over a simulated infrared connection.

1. Launch two instances of the emulator. One listens for incoming connections, while the other attempts to send an image.

For example, right-click ObexDemo, select Run With... and choose the device DefaultCldcPhone1. Repeat and choose DefaultCldcPhone2.

2. In the first emulator, launch the application then choose Receive Image. (Depending on your security level, the application warns that an OBEX connection allows other devices to talk to yours and asks, "Is it OK to make the connection?" Choose Yes.) Choose Start to run the application. The listener emulator displays a screen reading "Waiting for connection".
3. In the second emulator (the sender), choose Send Image and press the Start soft key. Select an image from the list and choose Send. (Depending on your security level, the application warns that the demo wants to make an outgoing client connection, and asks if it is OK. Choose Yes.) The Send Image utility uploads the image.
4. In the listening emulator, the utility displays information about the incoming image and asks "Would you like to receive it?" Choose yes.

The image you selected is transferred over the simulated infrared link and displayed on the first emulator.

JSR 135: Mobile Media API Support

JSR 135, the Mobile Media API (MMAPI), provides a standard API for rendering and capturing time-based media, like audio or video. The API is designed to be flexible with respect to the media formats, protocols, and features supported by various devices. See the following topics:

- [Section 18.1, "Media Types"](#)
 - [Section 18.1.1, "Media Capture"](#)
- [Section 18.2, "MMAPI MIDlet Behavior"](#)
- [Section 18.3, "Ring Tones"](#)
 - [Section 18.3.1, "Download Ring Tones"](#)
 - [Section 18.3.2, "Ring Tone Formats"](#)
- [Section 18.4, "Running AudioDemo"](#)
- [Section 18.5, "Running MMAPI Demos"](#)

For information on programming with MMAPI, see the following articles:

Mobile Media API Overview:

http://developers.sun.com/techtopics/mobile/apis/articles/mmapi_overview/

The J2ME Mobile Media API: <http://www.jcp.org/en/jsr/detail?id=135>

18.1 Media Types

The emulator's MMAPI implementation supports the following media types.

MIME Type	Description
audio/amr*	Adaptive Multi-Rate Narrow Band
audio/midi	MIDI files
audio/mpeg*	MP3 files
audio/mp4*	MP4 Audio files
audio/sp-midi	Scalable Polyphony MIDI
audio/x-tone-seq	MIDP 2.0 tone sequence
audio/x-wav*	WAV PCM sampled audio
image/gif	GIF 89a (animated GIF)

MIME Type	Description
video/3gpp*	Third generation mobile broadband with video
video/mpeg*	MPEG video
video/mp4*	MP4 video files
video/avi*	Video capture emulation and Audio-Video Interleaved files

In the previous table, an asterisk (*) indicates a media type that requires corresponding DirectShow filters to be installed on your system. For example, MP3 support might require an MP3 Splitter and an MP3 Decoder (these might be two separate DirectShow filters, or they might be combined in one filter). Any appropriate filters can be used, but Java ME SDK 3.0.5 has only been tested with filters from the K-Lite Mega Codec Pack 4.8.0. If no appropriate DirectShow filters are found on your system, JSR 135 Player creation for the media type might fail.

18.1.1 Media Capture

The Java ME SDK emulator supports audio and video capture. Audio capture is supported using the capture capabilities of the system upon which the emulator runs.

Video capture is supported by simulating a camera input.

Consult the [MobileMediaAPI](#) example application for details and source code that demonstrates how to capture audio and video.

18.2 MMAPI MIDlet Behavior

MIDlets have a lifecycle that is defined in the MIDP specification. MIDlets can be paused by events such as incoming phone calls. A well-behaved MIDlet releases important device resources when it is paused and reallocates or restarts those resources when the MIDlet is resumed. In the MMAPI arena, stop any Players that are rendering content when a MIDlet is paused.

The Java ME SDK prints a message to the console if you pause a MIDlet and it does not stop its running Players. You can test this feature using the Pausing Audio Test MIDlet in the [MobileMediaAPI](#) demonstration application.

The warning message is printed only once for each running emulator.

18.3 Ring Tones

MMAPI can be used to play ring tones, as demonstrated in [Section 18.5.1, "Simple Tones"](#) and [Section 18.5.2, "Simple Player"](#). The ring tone formats mentioned here are in common use. You can download ring tones or create your own.

18.3.1 Download Ring Tones

Ring tone files can be downloaded from many internet sites, including the following:

- <http://www.convertyourtone.com/>
- <http://www.phonezoo.com>

18.3.2 Ring Tone Formats

This section provides samples of several formats

- RTTTL, the Ringing Tones text transfer language format, is explained at
<http://www.convertyourtone.com/rtttl.html>
- Nokia Composer
This is a rendition of Beethoven's 9th symphony in Nokia Composer format:
16g1,16g1,16g1,4#d1,16f1,16f1,16f1,4d1,16g1,16g1,16g1,16#d1,
16#g1,16#g1,16#g1,16g1,16#g2,16#d2,16#d2,16#d2,4c2,16g1,16g1,16g1,
16d1,16#g1,16#g1,16#g1, 16g1,16f2,16f2,16f2,4d2
- Ericsson Composer
Beethoven's Minuet in G:
a b + c b + c b + c b + C p + d a B p + c g A
p f g a g a g a g A p b f G p a e F
Beethoven's 9th symphony theme:
f f f # C # d # d # d C p f f f # c # f # f f +# c + # c + # c # A
ff f c # f # f f # d + # d + # d
- Siemens Composer Format
Inspector Gadget theme:
C2(1/8) D2(1/16) Dis2(1/8) F2(1/16) G2(1/8)
P(1/16) Dis2(1/8) P(1/16) Fis2(1/8) P(1/16)
D2(1/8) P(1/16) F2(1/8) P(1/16) Dis2(1/8)
P(1/16) C2(1/8) D2(1/16) Dis2(1/8) F2(1/16)
G2(1/8) P(1/16) C3(1/8) P(1/16) B2(1/2) P(1/4)
C2(1/8) D2(1/16) Dis2(1/8) F2(1/16) G2(1/8) P(1/16)
Dis2(1/8) P(1/16) Fis2(1/8) P(1/16) D2(1/8) P(1/16)
F2(1/8) P(1/16) Dis2(1/8) P(1/16) C3(1/8) B2(1/16)
Ais2(1/8) A2(1/16) Gis2(1/2) G2(1/8) P(1/16) C3(1/2)
- Motorola Composer
Beethoven's 9th symphony:
4 F2 F2 F2 C#4 D#2 D#2 D#2 C4 R2 F2 F2 F2 C#2 F#2 F#2
F#2 F2 C#+2 C#+2 C#+2 A#4 F2 F2 F2 C2 F#2 F#2 F#2 F2
D#+2 D#+2 D#+2
- Panasonic Composer
Beethoven's 9th symphony:
444** 444** 444** 1111* 4444** 4444** 4444** 111*
0** 444** 444** 444** 1111** 4444** 4444** 4444**
444** 11** 11** 11** 6666* 444** 444** 444** 111**
4444** 4444** 4444** 444** 22** 22** 22**
- Sony Composer

Beethoven's 9th symphony:

```
444*****444****444****111#*****444#****444#****444#****  
111***** (JD) 0000444****444****444****111#*****444#****  
444#****444#****444****11#****11#****11#****666#****  
444****444****444****111****444#****444#****  
444#****444****22#****22#****22#****
```

18.4 Running AudioDemo

Demonstrates audio capabilities, including mixing and playing audio with an animation. Select a MIDlet from the list, and from the menu, select 1, Launch.

- **Audio Player.**
Select a sound clip and press the Play soft button. Click Back to return to the list of clips.
- **Bouncing Ball.** Select No Background and press the Play soft button. Two balls randomly bounce in the screen, emitting a tone whenever they contact a wall.
Wave background, tone seq background, and MIDI background play the same two-ball audio visual sequence with the additional audio background.
- **Mix Demo** shows that different audio formats can play simultaneously. Select a MIDlet and press the Play soft button.
Tone+Wav - The audio clip starts playing and the Tone soft button is displayed. Press the Tone button to hear a tone playing over the original audio clip.
Tone+ToneSeq - The audio clip starts playing and the Tone soft button is displayed. Press the Tone button to hear a tone playing over the original audio clip.
ToneSeq+Wav - The tone sequence and the wav sequence play simultaneously. Press the Pause soft button to interrupt, and press Play to resume.

18.5 Running MMAPI Demos

The MMAPI Demos application contains four MIDlets that showcase the SDK's multimedia capabilities:

18.5.1 Simple Tones

Simple Tones demonstrates how to use interactive synthetic tones. Select a sample, then click Play on the lower right.

- Short Single Tone and Long Single Tone use `Manager.playTone()` to play tones with different pitch.
- Short MIDI event plays a chord on the interactive MIDI device (locator "device://midi"). The `shortMidiEvent()` method of `MIDIControl` is used to trigger the notes of the chord.
- To run the MMAPI Drummer demo, click or type number keys (0-9). Each number plays a different sound.

18.5.2 Simple Player

The Simple Player application demonstrates the range of audio and video capabilities of the emulator. It includes sample files in a variety of formats and can play files from the emulator's persistent storage or from HTTP URLs.

The player portion uses a generic `javax.microedition.media.Player` interface. The player displays duration, media time, and controls for running the media file. If metadata is available in a file, the player enables you to view the information, such as author and title. In the case of MIDI files, if karaoke text is present in the file, it displays on the screen during play. Graphical user interface controls can be viewed on the display screen if applicable. You can access these controls by selecting one of the media samples in Simple Player, then pressing the Menu button to view and select the desired command.

Select Simple Player then click Launch. The demo includes the following media samples:

- Bong plays a short WAV file. You can adjust certain playback features, as described later in this document. The display shows the duration of the sound in *minutes:seconds:tenths* of a second, for example 00:17:5. This audio sample is a resource file in the MIDlet suite JAR file.
- MIDI Scale plays a sample musical scale. The display shows the title of the selected music file, the duration of the song, the elapsed time during playback, and the current tempo in beats per minute (bpm). This MIDI file is stored in the MIDlet suite JAR file.
- Simple Ring Tone plays a short sequence of Beethoven's Fifth Symphony. The display shows the title of the selected music file, the duration of the song, the elapsed time in seconds and tenths of a second during playback, and the current tempo in beats per minute (bpm). This ringtone file (.jts format) is stored in the MIDlet suite JAR file.
- WAV Music plays a brief audio file. The display shows the title of the audio file, the duration of the audio the elapsed time during playback, and the playback rate in percent. This WAV file is retrieved from an HTTP server.
- MIDI Scale plays a MIDI file that is retrieved from an HTTP server.
- The Animated GIF example shows an animated GIF that counts from 1 to 5. The file is stored in the MIDlet suite JAR file.
- Audio Capture from a default device lets you capture audio from a microphone or connected device. The sound is captured and played back on the speaker. To avoid feedback, use a headset.
- Video Capture Simulation simulates viewing input video such as might be possible on a device equipped with a camera.
- MPEG1 Video [http]. Plays an MPEG video found at <http://java.sun.com/products/java-media/mma/media/test-mpeg.mpg>.
- [enter URL] allows you to play back media files from arbitrary HTTP servers. Type a valid URL at the insertion point and click OK to play a file. If you want to open an HTTP directory from which to select media, be sure to add a slash to the end of the URL.

In addition, Simple Player parses ring tones in Ringing Tones text transfer language (RTTTL). See <http://www.convertyourtone.com/rtttl.html> for information on RTTTL.

The Simple Player includes a common set of commands that control media playback. The commands are available from the Simple Player menu, and some have associated keypad buttons. [Table 18-1](#) describes these commands, their availability, and their keypad equivalents. The commands may or may not be available depending on the media type that Simple Player is playing.

Note that a short list of commands and the corresponding keypad buttons is available in the Simple Player application itself. Just choose the Quick Help command from the menu.

Table 18-1 Simple Player Commands

Command	Menu Item	Description
Mute/Unmute	1	Turns off sound but the file continues to play. This command toggles to Unmute.
Play	2	Play.
Volume	3	Increases or decreases loudness.
META Data	4	Displays information provided by the media file such as copyright information, title, and track list.
Stop in 5 seconds	5	Pauses the audio play in five seconds when set during playback.
Loopmode	6	After playing, repeat.
Rate	7	Alters the rate of speed of playback.
Tempo	8	Increases or decreases the tempo of the tone sequence or MIDI file.
Pitch	9	Lowers or raises the notes in a MIDI file.
Skip Forward		Skips forward five percent of the duration of the media file. The sound track syncs to the video
Skip Backward		Skips backward five percent of the duration of the media file. The sound track syncs to the video.
Rewind		Returns to the start time of the audio playback.
Quick Help		Displays a list of commands and keypad buttons.

18.5.2.1 Video

The Video application illustrates how the emulator is capable of playing animated GIF files and capturing video. On a real device with a camera, video capture can be used to show the user what the camera sees.

Animated GIFs and video capture can be implemented using either a `Form Item` or a `Canvas`. The Video demonstration includes all the possibilities. [Animated GIF - Form \[jar\]](#) shows an animated GIF as a Form Item. The form also includes some information about the playback, including the current time. Choose the Snapshot command to take a snapshot of the running animation. The snapshot will be placed in the form following the animated GIF.

- **Animated GIF - Canvas [jar]** shows an animated GIF in a `Canvas`. A simple indicator shows the progress through the animation. Choose Snapshot to get a still image of the current appearance. The snapshot is shown briefly, then the display goes back to the animation.
- **Video Capture - Form** simulates capturing video from a camera or other source and showing it as an Item in a Form. Choose the Snapshot command to take a

snapshot of the captured video. The snapshot will be placed in the form following the video capture.

- **Video Capture** - Canvas simulates capturing video from a camera or other source and showing it in a Canvas. Choose Snapshot to get a still image of the current appearance. The snapshot is shown briefly, then the display goes back to the video capture.
- **MPEG1 Video** - Form, MPEG1 Video - Canvas

The MPEG1 applications obtain MPEGs from the web, so if you are behind a firewall, you must configure the emulator's proxy server settings, as described in the topic "[Section 3.4, "Configuring the Web Browser and Proxy Settings"](#)".

When you play the demo, expect to wait a few seconds while the demo obtains the data. The MPEG1 demos have the same behavior as Video Capture - Form and Video Capture - Canvas, respectively.

18.5.2.2 Attributes for MobileMediaAPI

The MobileMediaAPI applications have the following editable attributes. Right-click on the project and select Properties. Select Application Descriptor and view the Attributes tab.

Table 18-2 Descriptions of MMAPI-specific MIDlet attributes

Attribute	Description
PlayerTitle- <i>n</i>	Name of the <i>n</i> th media title to be played back by the Simple Player MIDlet.
PlayerURL- <i>n</i>	Location of the <i>n</i> th media title, PlayerTitle- <i>n</i> , to be played back by the Simple Player MIDlet.
VideoTest- <i>n</i>	The name of the <i>n</i> th media title to be played back by the Video application.
VideoTest-URL <i>n</i>	Location of the <i>n</i> th media title, VideoTest- <i>n</i> , to be played back by the Video application.

JSR 172: Web Services Support

The Java ME SDK emulator supports JSR 172, the J2ME Web Services Specification. JSR 172 provides APIs for accessing web services from mobile applications. It also includes an API for parsing XML documents.

See also:

[Section 19.1, "Generating Stub Files from WSDL Descriptors"](#)

[Section 19.2, "Creating a New Mobile Web Service Client"](#)

[Section 19.3, "Run JSR172Demo"](#)

19.1 Generating Stub Files from WSDL Descriptors

The NetBeans IDE provides a stub generator that automates creating source code for accessing web services that conform to the J2ME Web Services Specification. You can add stubs to any MIDP application.

Note: If you are using NetBeans 6.9.1, the "Mobility End to End" plugin must be installed.

If you are using NetBeans 7 or higher the "SOAP Web Services" plugin must be installed.

The following is a general procedure for adding stubs:

1. In the Projects window, expand the tree for a project.
2. Launch the Java ME Web Service Client wizard:

Right-click on the Source Packages node and select New > Java ME Web Service Client...

3. In the Generate J2ME Webservice Stub page, you can either:
 - Click Running Web Service and enter the URL for the WSDL
 - Click Specify the Local filename for the retrieved WSDL and browse to a file on your system.

In either case, you must enter a Package name, then click Finish. The new package appears in the project and includes an interface file and a stub file.

4. You can now edit your source files to call the content the stub provides, then build and run.

See [Section 19.2, "Creating a New Mobile Web Service Client"](#) for a step by step process, or see [Section 19.3, "Run JSR172Demo"](#) and view the demo source files.

19.2 Creating a New Mobile Web Service Client

This sample procedure creates a new project and adds a web service client. However, you can add a web service client to any MIDP project, it does not have to be new.

1. Select File > New Project, choose MIDP application, and click Next. Name your project and ensure Create Hello MIDlet is checked. Click Finish.
2. Right-click on the Source Packages node and select New > Java ME Web Service Client...
3. In the Generate J2ME Webservice Stub page:
 - Click Running Web Service and in the WSDL URL field, enter:
<http://www.xmlme.com/WSShakespeare.asmx?WSDL>
 - In the Package field, enter testws. This is the package name.Click Finish. The new package appears in Source Packages and includes `Shakespeare.java` and `Shakespeare_Stub.java`.
4. Edit `HelloMIDlet.java` as follows:
 - At the beginning, add the following import declaration:
`import testws.*`
 - Locate the `startApp()` method and replace its contents with the following code:

```
String text;
Shakespeare s = new Shakespeare_Stub();
try
{
    text = s.GetSpeech("Romeo");
} catch(java.rmi.RemoteException rex)
{
    text = "error";
    System.out.println(rex.getMessage());
}
TextBox t = new TextBox("Hello", text, 2048, 0);
t.addCommand(exitCommand);
t.setCommandListener(this);
display.setCurrent(t);
```

5. Build and run the project. You see a quote from Shakespeare's Romeo and Juliet on the device screen.

You can vary the above procedure to use a local WSDL file. Open the following web page in a browser:

<http://www.xmlme.com/WSShakespeare.asmx?WSDL>

Save it to a local file. For example, `c:\ws\WSShakespeare.wsdl`. Follow the procedure above, except at Step 4, specify the local file name.

19.3 Run JSR172Demo

JSR172Demo shows how to access a web service from a MIDlet. The web service is already running on an Internet server, and it conforms to the J2ME Web Services Specification.

If you are using a proxy server, you must configure the emulator's proxy server settings as described in [Section 3.4, "Configuring the Web Browser and Proxy Settings"](#). Build and run the example.

JSR172Demo contains a single MIDlet named Server Script. Launch it and follow the prompts. You can browse through simulated news headlines, all of which are retrieved from the web service.

JSR 177: Smart Card Security (SATSA)

The Security and Trust Services APIs (SATSA) provide smart card access and cryptographic capabilities to applications running on small devices. JSR 177 (the SATSA specification) defines four distinct APIs as optional packages:

- **SATSA-APDU** - Enables applications to communicate with smart card applications using a low-level protocol.
- **SATSA-JCRMI** - Provides an alternate method for communicating with smart card applications using a remote object protocol.
- **SATSA-PKI** -Enables applications to use a smart card to digitally sign data and manage user certificates.
- **SATSA-CRYPTO** - A general-purpose cryptographic API that supports message digests, digital signatures, and ciphers.

The Java ME SDK emulator fully supports SATSA. This topic describes how you can use the Java ME SDK to work with SATSA in your own applications.

For a more general introduction to SATSA and using smart cards with small devices, see the *SATSA Developer's Guide*, which is available at
<http://download.oracle.com/javame/config/cldc/opt-pkgs/api/security/satsa-dg>.

If you need to develop your own Java Card applications, download the Java Card Development Kit, available at
<http://www.oracle.com/technetwork/java/javacard/overview/index.html>. This kit is for Windows.

20.1 Card Slots in the Emulator

Real SATSA devices are likely to have one or more slots that house smart cards. Applications that use SATSA to communicate with smart cards need to specify a slot and a card application.

The Java ME SDK emulator is not a real device and, therefore, does not have physical slots for smart cards. Instead, it communicates with a smart card application using a socket protocol. The other end of the socket might be a smart card simulator or it might be a proxy that talks with real smart card hardware.

The Java ME SDK emulator includes two simulated smart card slots. Each slot has an associated socket that represents one end of the protocol that is used to communicate with smart card applications.

The default card emulator host name is localhost, and the default ports are 9025 for slot 0 and 9026 for slot 1. These port defaults are a property of the device. To change

the defaults in the user interface, right click on the device in the Device Selector, and select Properties. By default the Properties window is docked on the upper right of the Java ME SDK interface. You can also change them in the device's property file:

userhome\Application Data\javame-sdk\3.0.5\directory-number

Edit the `device.properties` file and modify this line:

```
runtime.internal.com.sun.io.j2me.apdu.hostsandports =
localhost:9025,localhost:9026
```

20.2 Java Card Platform Simulator (cref)

The Java ME SDK includes the Java Card Platform Simulator, which you can use to simulate smart cards in the Java ME SDK emulator's slots. The Java Card Platform Simulator is found in the following location:

installdir\bin\cref.exe

Hereafter we refer to it as simply `cref`. The basic procedure for testing SATSA applications with the Java ME SDK is as follows:

1. Start `cref` with a Java Card platform application.
2. Start the emulator.

When a SATSA application attempts to communicate with a smart card, it uses a socket connection to communicate with `cref`.

It's important, therefore, to make sure that you start `cref` with the same port number as one of the slot port numbers you specified in the Java ME SDK preferences.

For example, to run `cref` on port 9025 with a prebuilt memory image, use a command line similar to this:

```
start cref -p 9025 -i memory_image.eeprom
```

The Java ME SDK includes a demonstration application, `Mohair`, which illustrates how to use SATSA. For detailed instructions on running `Mohair`, see [Section 20.4.4, "MohairMIDlet"](#).

20.3 Adjusting Access Control

Access control permissions and PIN properties can be specified in text files. When the first APDU or Java Card RMI connection is established, the implementation reads the ACL and PIN data from the `acl_slot-number` in the `workdir\emulator-instance\appdb` directory. For example, an access control file for slot 0 might be:

```
Documents and Settings\user\javame-sdk\3.0.5\work\emulator-instance\appdb\acl_0
```

If the file is absent or contains errors, the access control verification for this slot is disabled.

The file can contain information about PIN properties and application permissions.

20.3.1 Specifying PIN Properties

PIN properties are represented by a `pin_data` record in the access control file.

```
pin_data {
```

```

id number
label string
type      bcd | ascii | utf | half-nibble | iso
min       minLength
max       maxLength
stored    storedLength
reference byte
pad       byte - optional
flag      case-sensitive | change-disabled | unblock-disabled
           needs-padding | disable-allowed | unblockingPIN
}

```

20.3.2 Specifying Application Permissions

Application permissions are defined in access control file (acf) records. The record format is as follows:

```

acf AID fnumbers separated by blanks {
    ace {
        root CA name
        ...
        apdu {
            eight numbers separated by blanks
            ...
        }
        ...
        jc.rmi {
            classes {
                classname
                ...
            }
            hashModifier string
            methods {
                method name and signature
                ...
            }
        }
        ...
        pin_apdu {
            id number
            verify | change | disable | enable | unblock
            four hexadecimal numbers
            ...
        }
        ...
        pin_jc.rmi {
            id number
            verify | change | disable | enable | unblock
            method name and signature
            ...
        }
        ...
    }
}

```

The `acf` record is an Access Control File. The AID after `acf` identifies the application. A missing AID indicates that the entry applies to all applications. The `acf` record can

contain ace records. If there are no ace records, access to an application is restricted by this acf.

The ace record is an Access Control Entry. It can contain root, apdu, jcrmi, pin_apdu, and pin_jcrmi records.

The root record contains one CA name. If the MIDlet suite was authorized using a certificate issued by this CA, this ace grants access to this MIDlet. A missing root field indicates that the ace applies to all identified parties. One principal is described by one line. This line must contain only the word root and the principal name, for example:

```
root CN=thehost;OU=JCT;O=dummy CA;L=Santa Clara;ST=CA;C=US
```

The apdu or jcrmi record describes an APDU or Java Card RMI permission. A missing permission record indicates that all operations are allowed.

An APDU permission contains one or more sequences of eight hexadecimal values, separated by blanks. The first four bytes describe the APDU command and the other four bytes are the mask, for example:

```
apdu {  
    0 20  0 82  0 20  0 82  
    80 20  0 0 ff ff  0 0  
}
```

The Java Card RMI permission contains information about the hash modifier (optional), class list, and method list (optional). If the list of methods is empty, an application is allowed to invoke all the remote methods of interfaces in the list of classes, for example:

```
jcrmi {  
    classes {  
        com.sun.javacard.samples.RMIDemo.Purse  
    }  
    hashModifier zzz  
    methods {  
        debit(S)V  
        setAccountNumber([B)V  
        getAccountNumber() [B  
    }  
}
```

All the numbers are hexadecimal. Tabulation, blank, CR, and LF symbols are used as separators. Separators can be omitted before and after symbols { and }.

The pin_apdu and pin_jcrmi records contain information necessary for PIN entry methods, which is the PIN identifier and APDU command headers, or remote method names.

20.3.3 Access Control File Example

```
pin_data {  
    label Unblock pin  
    id      44  
    type   utf  
    min     4  
    stored  8  
    max     8  
    reference 33
```

```

    pad      ff
    flag    needs-padding
    yflag   unblockingPIN
}
pin_data {
    label   Main pin
    id      55
    type    half-nibble
    min     4
    stored   8
    max     8
    reference 12
    pad      ff
    flag    disable-allowed
    flag    needs-padding
}
acf a0 0 0 0 62 ff 1 {
    ace {
        root CN=thehost;OU=JCT;O=dummy CA;L=Santa Clara;ST=CA;C=US

        pin_jcrami {
            id 55
            verify enterPIN([B)S
            change changePIN([B[B)S
            disable disablePIN([B)S
            enable enablePIN([B)S
            unblock unblockPIN([B[B)S
        }
    }
}

acf a0 0 0 0 62 ee 1 {
    ace {
        root CN=thehost;OU=JCT;O=dummy CA;L=Santa Clara;ST=CA;C=US

        pin_apdu {
            id 55
            verify 1 2 3 1
            change 4 3 2 2
            disable 1 1 1 3
            enable 5 5 5 4
            unblock 7 7 7 5
        }
    }
}

acf a0 0 0 0 62 3 1 c 8 1 {
    ace {
        root CN=thehost;OU=JCT;O=dummy CA;L=Santa Clara;ST=CA;C=US

        jcrami {
            classes {
                com.sun.javacard.samples.RMIDemo.Purse
            }
            hashModifier xxx
            methods {
                setAccountNumber([B)V
                getBalance()S
                credit(S)V
            }
        }
    }
}

```

```
        }
    }
    ace {
        jcrmi {
            classes {
                com.sun.javacard.samples.RMIDemo.Purse
            }

            debit(S)V
            getAccountNumber() [B
        }
    }
}

acf a0 00 00 00 62 03 01 0c 02 01 {
    ace {
        root CN=thehost;OU=JCT;O=dummy CA;L=Santa Clara;ST=CA;C=US
        apdu {
            0 20 0 82 0 20 0 82
            80 20 0 0 ff ff 0 0
        }
        apdu {
            80 22 0 0 ff ff 0 0
        }
    }
}
acf a0 00 00 00 62 03 01 0c 02 01 {

    ace {
        apdu {
            0 20 0 82 ff ff ff ff
        }
    }
}

acf a0 00 00 00 62 03 01 0c 06 01 {

    ace {
        apdu {
            0 20 0 82 ff ff ff ff
        }
    }
}
```

20.4 Running SATSDemos

SATSDemos includes demonstrations of SATSA, the Security and Trust Services APIs. Most of the demonstrations show how to communicate with a smart card. The emulator can communicate with a simulated smart card using a socket protocol. The smart card simulator, `cref`, is included with the SDK, as discussed in [Section 20.2, "Java Card Platform Simulator \(cref\)".](#)

For each SATSA demo, start with this sequence:

1. Start the instance(s) of `cref` from the command line.
2. Be sure to set the project security domain to maximum.

Right-click on the project, select Properties and choose Running. Enable Regular execution and check Specify the Security Domain. Choose maximum from the list.

3. Run the project.

20.4.1 APDUMIDlet

This MIDlet demonstrates communication with a smart card using Application Protocol Data Units (APDUs), small packets of data. APDUMIDlet expects to find two simulated smart cards. You can run the smart card simulator using `cref`, which is part of the Java Card Development Kit. See [Section 20.2, "Java Card Platform Simulator \(cref\)"](#).

The `Mohair` application includes pre-built memory images that you can use with `cref`. The memory images contain Java Card applications with which `Mohair` interacts. The memory images are in the root directory of the `Mohair` project.

1. Right-click on the project, select Properties, and choose Running. Enable Regular execution and check Specify the Security Domain. Choose maximum from the list.

2. Start up two instances of `cref`, one for each simulated card slot (assuming the current directory is the SDK installation directory):

```
start installdir\bin\cref -p 9025 -i apps\SATSDemos\demo2.eeprom
```

```
start installdir\bin\cref -p 9026 -i apps\SATSDemos\demo2.eeprom
```

3. Once you have the two smart card simulators running, run SATSDemos. Select APDUMIDlet, select the Menu soft key and select Launch (1). Press Go when prompted.

20.4.2 SATMIDlet

SATMIDlet demonstrates smart card communication with a slight variation on APDU communication.

1. To set up the simulated smart card, use `cref`, very much like you did for APDUMIDlet. This time you don't have to specify a port number, and the memory image is different:

2. Right-click on the project, select Properties, and choose Running. Enable Regular execution and check Specify the Security Domain. Choose maximum from the list.

3. Start `cref`:

```
start installdir\bin\cref -i apps\SATSDemos\sat.eeprom
```

Note that the port number arguments (9025 and 9026 in this example) must match the SATSA port numbers. Also, make sure you use the correct path to `sat.eeprom`.

4. Once you have the smart card simulator running, run SATSDemos. Select SATMIDlet, select the Menu soft key and select Launch (1). Press Go when prompted.

20.4.3 CryptoMIDlet

CryptoMIDlet demonstrates the general cryptographic features of SATSA. It does not interact with a smart card in any way. Choose the MIDlet and launch it to see the cryptography results. Use the up and down navigation keys to scroll the display.

20.4.4 MohairMIDlet

MohairMIDlet has two functions. The first, "Find slots", displays all the available card slots. Each slot has a number followed by 'C' or 'H' indicating whether the slot is cold-swappable or hot-swappable. After viewing the slots select Back to return to the first screen.

The second part of MohairMIDlet, SATSA-PKI Sign test, uses a smart card to generate a digital signature. As with the earlier demonstrations, you need to run `cref` with the right memory image to prepare for the connection from MohairMIDlet.

1. Right-click on the project, select Properties, and choose Running. Enable Regular execution and check Specify the Security Domain. Choose maximum from the list.

2. Type the following from the SDK installation directory:

```
start installdir\bin\cref -i apps\SATSDemos\sat.eeprom
```

3. In the emulator, select SATSA-PKI Sign test. The following confirmation message appears:

This certificate will be used: MohairAuth

Select the OK soft key.

4. For PIN 1, type: 1234

Select the OK soft key. The following confirmation message appears:

This string will be signed: JSR 177 Approved

5. Select the OK soft key. The following confirmation message appears:

This certificate will be used: MohairAuth

Select the OK soft key.

6. For non repudiation key 1 PIN, type: 2345

Select the soft menu and choose OK (option 2).

20.4.5 Running SATSAJCRMIDemo

This application contains a single MIDlet, `JCRMIMIDlet`, which shows how to communicate with a card application using Java Card RMI, a card-friendly remote object protocol. As with some of the MIDlets in `SATSDemos`, you need to start up `cref` with an appropriate memory image.

1. Right-click on the project, select Properties, and choose Running. Enable Regular execution and check Specify the Security Domain. Choose maximum from the list.

2. Start `cref` from the SDK installation directory as follows:

```
start installdir\bin\cref -p 9025 -i apps\SATSDemos\demo2.eeprom
```

3. Now run `JCRMIMIDlet` to see how your application can communicate with a distributed object on the card.

JSR 179 and 293: Location API Support

The JSR 179 Location API gives applications the opportunity to use a device's location capabilities. For example, some devices include Global Positioning System (GPS) hardware. Other devices might be able to receive location information from the wireless network. The Location API provides a standard interface to location information, regardless of the underlying technique.

In the Location API, a *location provider* encapsulates a positioning method and supplies information about the device's location. The application requests a provider by specifying required criteria, such as the desired accuracy and response time. If an appropriate implementation is available, the application can use it to obtain information about the device's physical location.

JSR 293 extends 179, supporting all 179 capabilities.

The Java ME SDK includes a simulated location provider. You can use the emulator's External Events Generator to specify where the emulator should think it is located. In addition, you can configure the properties of the provider itself, and you can manage a database of landmarks.

The JSR 293 implementation supports extended landmark features including the LandmarkStore 2.0 database which has access to a native database of landmarks. This implementation includes:

- increased search capabilities
- private and public landmark stores
- LandmarkStore listener
- global landmark categories

For an explanation of this implementation, see the *Oracle Java Wireless Client Porting Guide* and the Location API 2.0 at <http://jcp.org/en/jsr/detail?id=293>.

21.1 Setting the Emulator's Location at Runtime


You can specify the simulated location of the emulator while it is running. To do this, choose Device > Location. This raises the external events generator with the Location tab selected.

In the Location area of the tab, you can fill in values for the latitude, longitude, altitude, speed, and course. Applications that use the Location API can retrieve these values as the location of the emulator.

For more elaborate testing, you can set up a location script that describes motion over time. Location scripts are XML files consisting of a list of locations, called *waypoints*, and associated times. The Java ME SDK determines the current location of the

emulator by interpolating between the points in the location script. Here, for example, is a simple location script that specifies a starting point (time="0") and moves to a new point in ten seconds:

```
<waypoints>
  <waypoint time="0"
    latitude="14" longitude="50" altitude="310" />
  <waypoint time="10000"
    latitude="14.5" longitude="50.1" altitude="215" />
</waypoints>
```



The altitude measurement is in meters, and the time values are in milliseconds.

Use a text editor to create your location script. You can load it into the external event window by pressing the Browse button next to the Script field. Immediately below are controls for playing, pausing, stopping, and moving to the beginning and end of the location script. You can also drag the time slider to a particular point.

Some devices are also capable of measuring their orientation. To make this kind of information available to your application, change the State field in the Orientation box to Supported and fill in values for azimuth, pitch, and roll. The Magnetic Orientation check box indicates whether the azimuth and pitch measurements are relative to the Earth's magnetic field or relative to true north and gravity.

To test how your application handles unexpected conditions, try changing the State field in the Location Provider box to Temporarily Unavailable or Out of Service. When your application attempts to retrieve the emulator's location, an exception is thrown and you can see how your application responds.

21.2 Running the CityGuide Sample Project


CityGuide demonstrates how to use the Location API (JSR 179). It shows a walker's current position superimposed on a city map. The walker moves around the city and landmarks are highlighted and identified as the walker approaches. In this demo we get the walker's location from an XML script named `citywalk.xml` (the event file) that submits the device location information.

Because location prompts occur frequently, it is best to run this demonstration in manufacturer (trusted) mode, as explained in "[Section 12.1, "Security Domains"](#)". In the user interface, right-click on your project and select the Running category. Select Specify the Security Domain, and select manufacturer or maximum.

1. Open and run the CityGuide project. In the emulator, launch the CityGuide MIDlet. Click Load to view the map page.



2. In the emulator, choose Device > Location. On the Location tab, click the Browse button. Select the following event file: *installldir\apps\CityGuide\citywalk.xml*.
The player buttons at the bottom of the window are now active. Press the green play button (right-pointing triangle) to run the script.
3. The display shows four types of landmarks: restaurants, museums, shops, and theaters.
To adjust the landmark display, open the soft menu and choose the Settings command. Use the navigation keys to highlight a category, then use Select to check or uncheck an item.
When you are near a landmark (shown highlighted on the map), open the soft menu and choose the Detail command to see more information.



21.3 Running the CityGuide2_0 Sample Project

The City Guide2_0 example works much like the CityGuide sample project. The difference is that it implements the Landmark export function, which exports landmarks using an MMS text message.

1. Open and run the CityGuide2_0 project. In the emulator, launch the CityGuide MIDlet. Click Load to view the map page.
2. In the emulator, choose Device > Location. On the Location tab, click the Browse button. Select the following event file:


installldir\apps\CityGuide2_0\citywalk.xml

The player buttons at the bottom of the window are now active. Press the green play button (right-pointing triangle) to run the script.

3. The display shows five types of landmarks: gc_public_service, restaurants, museums, shops, and theaters. gc_public_service indicates wireless service is detected and landmark export is possible.

When running the script you can see the wireless service detected between 28 seconds and one minute twenty seconds.

4. Run the CityGuide2_0 project in a second emulator. At the introduction page, press the Import soft button. The application displays "Waiting for MMS".
5. In the first emulator, open the menu and choose option 3, Export. Set the phone number to point to the second emulator.



From the menu, select option 2, Send.

6. In the second emulator, the message changes to Importing MMS and you see a progress bar as the transmission completes.

JSRs 120 and 205: Wireless Messaging

The Java ME SDK supports the Wireless Messaging API (WMA) with a sophisticated simulation environment. WMA 1.1 (JSR 120) enables MIDlets to send and receive Short Message Service (SMS) or Cell Broadcast Service (CBS) messages. WMA 2.0 (JSR 205) includes support for MMS messages as well.

This chapter describes the tools you can use to develop WMA applications. It begins by showing how to configure the emulator's support of WMA. Next, it describes the WMA console, a tool for testing WMA applications.

Many of the tasks in this topic can also be accomplished from the command line. See [Section 22.3, "Running WMA Tool"](#) and [Section 22.2.3, "Sending SMS Messages From WMA Console to an Emulator and Back"](#).

22.1 Using the WMA Console to Send and Receive Messages

The WMA console is a tool that enables you to send messages to and receive messages from applications that use JSRs 120 or 205. You can, for example, use the WMA console to send SMS messages to a MIDlet running on the emulator.

See [Section 22.1.2, "WMA Console Interface"](#).

22.1.1 Launching the WMA Console

To launch the WMA console, select Tools > Java ME > WMA Console. Messages can be sent from the WMA Console to an emulator instance.


To open the WMA Output window, select Window > Output > WMA Console Output. This window displays messages received from an emulator.

Note, WMA console operations can also be performed from the command line. See [Section 22.3, "Running WMA Tool"](#).

22.1.2 WMA Console Interface

The console has a phone number, and it is displayed as part of the WMA Console tab label (for example, 987654321).

The WMA Console user interface has a tab for sending messages and an output window that displays incoming messages.



To set the phone number, select Tools > Options > Miscellaneous. On the WMA Console tab, edit the Assigned Phone Number field and click OK. If the number is available it is assigned to the console immediately. If the number is in use it is assigned to the console the next time you restart the SDK.

22.1.3 Emulator Phone Numbers

Each running instance of the emulator has a simulated phone number that is shown in the emulator window. The phone numbers are important because they are used as addresses for WMA messages.

22.1.4 Sending a Text or Binary SMS Message

To launch the WMA console, select Tools > Java ME > WMA Console. To open the WMA Output window, select Window > Output > WMA Console Output.

To send a text SMS message, click Send SMS. The send window appears. The window automatically lists the phone numbers of all running emulator instances. Select one or more destinations and enter a port number if you wish (the default is 50000). Type your message and click Send.

To send the contents of a file as a binary message, click Send SMS to bring up the send window. Click the Binary SMS tab. Selecting recipients is the same as for sending text SMS messages. You can type in the path of a file directly, or click Browse to open a file chooser.

22.1.5 Sending Text or Binary CBS Messages

Sending CBS messages is similar to sending SMS messages except that you don't need to choose recipients. To send a text or binary CBS message, click Send CBS in the WMA console. Specify a message identifier and enter the content of your message.

22.1.6 Sending MMS Messages

MMS messages consist of one or more files, usually images or sounds. An MMS message can be sent to multiple recipients. To send an MMS message from the WMA console, click the Send MMS button.

The window for composing MMS messages has two tabs, one for recipients and one for content. On the Header tab, begin by filling in a subject and recipient.

To add more recipients, click the Add button. For example, to send a message to a running emulator whose number is 5550001, type 5550001 in the To field.

To remove a recipient, first select its line, then click Remove.

To add optional media files (Parts) to the message, click the Parts tab and click Add. Most media files will have information to fill the Content Location, Content ID, Mime-Type (text/plain for simple MMS), and Encoding fields, but you can edit these fields as well. The default ID for the demo is `example.mms.MMSDemo`.

To remove a part, select it and press Remove.

22.1.7 Receiving Messages in the WMA Console

The WMA console window has its own phone number displayed on the WMA Console tab. You can send messages from your applications running on the emulator to the WMA console.

Received messages are displayed in the WMA output window.

22.2 Running WMADemo

The WMADemo sample project shows how to send and receive SMS, CBS, and MMS messages. Messages can be exchanged between emulator instances and can be generated or received using the WMA console utility.

22.2.1 WMADemo Push Registry Values

The push registry determines how the demo establishes certain types of connections. This information is set in the Application Descriptor. To view it, right-click on the WMA Demo project and select properties. In the properties window, select the Application Description category and view the Push Registry tab.

- For SMS messages the port number is 50000.
- For CBS Messages, the Message Identifier is 50001.
- For MMS messages, the application ID is `example.mms.MMSDemo`.

22.2.2 Running WMADemo OTA

Because this sample makes use of the push registry, you can't see all of its features with the standard Run process. Use the Run via OTA feature to install the application into the emulator using a process that mirrors how applications are installed on real devices.

1. Right-click the WMADemo project and select Properties from the context menu.
2. Select the Running Category and choose the Execute through OTA radio button. Click OK.

3. Now run WMADemo in an emulator. There will be a download, then you see an alert that reads, "Is it OK to automatically start the application? WMA Demo wants to register itself to be automatically started. Is it OK to be automatically started?" To proceed, choose Yes.

Wait a few seconds for the application to download to the emulator and register itself.

The application home screen shows the MIDlets you can launch: SMS Send, SMS Receive, CBS Received, MMS Send and MMS Receive.

22.2.3 Sending SMS Messages From WMA Console to an Emulator and Back

In this demo you send messages between the WMA Console and the client demo application running on the emulator. Using the WMA console to send messages to the emulator exercises the push registry.

1. To launch the WMA console, select Tools > Java ME > WMA Console. To open the WMA Output window, select Window > Output > WMA Console Output. The WMADemo should be running in the emulator, as described in [Section 22.2.2, "Running WMADemo OTA"](#).

2. Click on the Send SMS button in the WMA console window.

Choose the number that corresponds to the emulator, by default this means checking the box in front of 123456789. If you're not sure what number the emulator is using, look for a number above the emulator screen.

Fill in a port number of 50000.

Type your text message in the Message field and click on Send.

3. The emulator asks if it is OK if the WMADemo interrupts and if it can be started. You might receive several permission requests based on your firewall settings.

Choose Yes. The SMSReceive MIDlet is launched and immediately displays the incoming SMS message.

4. To type a return message, press the Reply soft button. Type a message and select Send. You are asked to give permission because there is a cost to your phone number. In the IDE, look in the WMA Output Window to confirm that your reply has been received. (The output window is typically displayed below the WMA Console. Be sure to click the WMA Output Window tab.)

22.2.4 Sending CBS Messages from WMA Console to an Emulator

This process is similar to sending SMS Messages. Instead of specifying a port number you specify a Message Identifier.

1. To launch the WMA console, select Tools > Java ME > WMA Console. To open the WMA Output window, select Window > Output > WMA Console Output.

2. Click on the Send CBC button in the WMA console window.

Supply a Message Identifier of 50001.

Type your text message or attach a binary message and click on Send.

3. The emulator asks if it is OK if the WMADemo interrupts and if it can be launched. You might receive several permission requests based on your firewall settings.

Choose Yes. The CBSReceive MIDlet is launched and immediately displays the incoming message. Click Exit to close the MIDlet.

22.2.5 Sending MMS Messages from WMA Console to an Emulator

To send an MMS message from the WMA console to the emulator, make sure that WMADemo has been installed using Run via OTA.

1. From the WMADemo home screen, choose MMS Receive. The emulator displays: Receiving... Waiting for MMS on applicationID example.mms.MMSDemo...
2. In the WMA console, click on Send MMS to open the MMS composition window. The Header tab is open by default. Supply any message subject, the application ID example.mms.MMSDemo, and the telephone number of the running emulator. If only one emulator is running, that number is displayed in the To field by default. If you don't see your number, click the Add button to add it.
3. Click on the Parts tab. The WMA console allows you to select files to send as parts of the MMS message. Click Add and use the file browser to find the file you want to send. Click OK.
4. Click on Send to send the message.

The image and its information are displayed in the emulator.

22.3 Running WMA Tool

To send and receive SMS, CBS, and MMS messages from the command line, use

installdir\bin\wma-tool

The device manager must be running before you launch `wma-tool`.

When the tool is started, it outputs the phone number it is using.

Each protocol has send and receive commands. The requested command is passed to the tool as a first argument. Possibilities are:

- `receive`
- `smsreceive` - receives SMS messages
- `cbsreceive` - receives CBS messages
- `mmsreceive` - receives MMS messages
- `smssend` - sends SMS message
- `cbssend` - sends CBS message
- `mmssend` - sends MMS message

The `*send` commands send the specified message and exit. The `*receive` commands print incoming messages until they are explicitly stopped.

Each command has its own arguments.

22.3.1 `smsreceive`

`smsreceive [-o outputDir] [-t timeout] [-q]`

`-o outputDir`. Store binary contents to `outputDir`.

`-t timeout`. Non-interactive mode, waits only `timeout` seconds for messages.

`-f` Store text contents as files instead of printing them.

`-q` Quiet mode.

Example

Start the emulator from the bin directory:

```
emulator.exe -Xdevice:DefaultCldcPhone1  
-Xdescriptor:..\apps\WMADemo\dist\WMADemo.jar
```

Start wma-tool from the bin directory:

```
C:\Java_ME_platform_SDK_3.0.5\bin>wma-tool smsreceive  
WMA tool started with phone number: 123456803  
press <Enter> to exit.
```

In the emulator run the SMS Send MIDlet and send a message to the WMA console. The console receives the message as follows:

```
SMS Received:  
    From: 123456789  
    Port: 50000  
    Content type: Text  
    Encoding: GSM7BIT  
    Content: from emulator to wma-tool  
Waiting for another message, press <Enter> to exit.
```

22.3.2 cbsreceive

```
cbsreceive [-o outputDir] [-t timeout] [-q]  
-o outputDir. Store binary contents to outputDir.  
-t timeout. Non-interactive mode, waits only timeout seconds for messages.  
-f Store text contents as files instead of printing them.  
-q Quiet mode.
```

22.3.3 mmsreceive

```
mmsreceive [-o outputDir] [-t timeout] [-q]  
-o outputDir. Store binary contents to outputDir.  
-t timeout. Non-interactive mode, waits only timeout seconds for messages.  
-f Store text contents as files instead of printing them.  
-q Quiet mode.
```

22.3.4 smssend

```
smssend target_phone target_port message_content  
■ target_phone  
    Phone number of the target phone. Mandatory first argument.  
■ target_port  
    Port of the target phone. Mandatory second argument.  
■ message_content  
    Mandatory third argument. Can have one of these two forms:  
        ■ text: text of the text message
```

- **-f file**: sends content of the specified file as a binary message.

22.3.5 cbssend

cbssend *message_id* *message_content*

- *message_id*
ID of the message. Mandatory first argument.
- *message_content*
Mandatory second argument. Can have one of these two forms:
 - **text**: text of the text message
 - **-f file**: sends content of the specified file as a binary message.

22.3.6 mmssend

```
mmssend <application id> <subject>
      [-to <targetphone>]* [-cc <target phone>]* [-bcc <targetphone>]*
```

[**-part { <part_from_file> | <part_from_text> }**]*

Each part is defined by *name=value* pairs delimited by a semicolon ";" separator.

Part Variables

To create *part_from_file*, define the following variables.

- **file**
File to send as a message part.
- **mimeType**
Mime type of the file.

To create *part_from_text*, define the following variable:

- **text**
Text to send as a message part. *mimeType* will be set to *text/plain*.
- **-to target_phone**
"to" target phone number. Any number of these options can be used.
- **-cc target_phone**
"cc" target phone number. Any number of these options can be used.
- **-bcc target_phone**
"bcc" target phone number. Any number of these options can be used.

Part from Text Options

Separate options with semicolons. For example:

- **-part contentId=content ID; encoding=encoding; text=text**

Appends text part to the message. Any number of these arguments can be used.
Contains the following options:

- **content ID**: content ID of this message part
- **encoding**: Sent text encoding. Only relevant for "text/plain." Mime type defaults to UTF8.

Part from File Options

`-part mimeType=mime type; contentId=content ID; file=file name`

- Appends binary part to the message with content loaded from the given file. Any number of these arguments can be used.

Separate the options with a semicolon.

- *content id*: content ID of this message part
- *mime type*: mime type of this message part
- *file name*: file with content of this message part
- *fileEncoding*: Encoding of text in the file, only relevant for "text/plain", only applies if the file argument is present. Defaults to the value of the encoding variable.

Example:

```
mmssend MyAppId MySubject -to 987654321
    -part text="text part" -part file=Duke.png:mimeType=image/png
```

JSR 184: Mobile 3D Graphics

The Mobile 3D Graphics API for J2ME, (JSR 184) provides 3D graphics capabilities with a low-level API and a high-level scene graph API. This chapter provides a brief overview and general guidelines for working with JSR 184.

JSR 184 is a specification that defines the Mobile 3D Graphics (M3G) API for the J2ME. This API provides 3D functionality in a compact package that's appropriate for CLDC/MIDP devices. The API provides two methods for displaying 3D graphics content:

The *immediate mode* API makes it possible for applications to directly create and manipulate 3D elements.

Layered on top of this is a *scene graph* API, also called *retained mode*, that makes it possible to load and display entire 3D scenes that are designed ahead of time.

For more information, consult the JSR 184 specification at
<http://jcp.org/en/jsr/detail?id=184>.

23.1 Choosing a Graphics Mode

Applications are free to use whichever approach is most appropriate or to use a combination of the retained mode and immediate mode APIs.

JSR 184 provides a standard API for CLDC/MIDP devices, enabling a new generation of 3D applications. The immediate mode API, in turn, is compatible with OpenGL ES, a standard lightweight API for 3D graphics. See <http://khronos.org/> for more information on OpenGL ES.

23.1.1 Immediate Mode

Immediate mode is appropriate for applications that generate 3D graphics content algorithmically, such as scientific visualizations or statistical graphs. The application creates 3D objects and manipulates them directly.

For an example of immediate mode, see the `Life3D` MIDlet in the `Demo3D` example application.

23.1.2 Retained Mode

Most applications, particularly games, use the retained mode or scene graph API. In this approach, a graphic designer or artist uses 3D modeling software to create a scene graph. The scene graph is saved in the JSR 184 file format. The scene graph file is bundled with the application. At runtime, the application uses the scene graph API to load and display the file.

Applications can manipulate parts of a loaded scene graph to animate characters or create other effects. The basic strategy is to do as much work as possible in the modeling software. At runtime, the application can grab and manipulate parts of the scene graph, which can also include paths for animation or other effects.

For an example of retained mode, see the `retainedmode` MIDlet in the `Demo3D` example application.

23.2 Quality Versus Speed

One of the challenges of MIDP development is the constrained environment of typical devices. Compared to desktop computers, MIDP devices have slow processors and little memory. These challenges extend into the arena of 3D graphics. To accommodate a wide variety of implementations, the JSR 184 specification provides various mechanisms to make the display of a 3D scene as efficient as possible.

One approach is *scoping*, a technique where you tell the 3D graphics implementation when objects are not going to interact with each other. For example, if you defined a scene graph for a house, you could use scoping to specify that the light in the basement doesn't affect the appearance of the bedroom on the second floor. Scoping simplifies the implementation's task because it reduces the number of calculations required to show a scene.

In general, the best way to improve the rendering speed of 3D scenes is to make some compromises in quality. The Mobile 3D Graphics API includes *rendering hints* so that applications can suggest how the implementation can compromise quality to improve rendering speed.

23.3 Content for Mobile 3D Graphics

Most mobile 3D applications use scene graphs in resource files to describe objects, scenes, and characters. Usually it is not programmers but graphic designers or artists who create the scene graphs, using standard 3D modeling tools.

Several vendors offer tools for authoring content and converting files to the JSR 184 format.

Because it is relatively difficult to create and manipulate 3D graphics content in an application using the immediate mode API, most applications rely as much as possible on a scene graph file. By putting as much as possible into the scene graph file at design time, the application's job at runtime is considerably simplified.

23.4 Running Demo3D Samples

`Demo3D` contains MIDlets that demonstrate JSR 184 features.

23.4.1 Life3D

`Life3D` implements the popular Game of Life in three dimensions. Live cells are represented by cubes. Each cell has 26 possible neighbors (including diagonals). For each step of the animation, cells with fewer than four neighbors die of loneliness, while cells with more than five neighbors die of overcrowding. An empty cell with exactly four neighbors becomes a new live cell.

The view of the playing board rotates slowly so you can view the board from all angles.

The keypad buttons in [Table 23-1](#) provide control over the game.

Table 23-1 Controls for *Life3D*

Button	Description
0	Pause the animation.
1	Resume the animation at its default speed.
2	Speed up the animation.
3	Slow down the animation.
4	Choose the previous preset configuration from an arbitrary list. The name of the configuration is shown at the top of the screen.
5	Choose the next preset configuration from the list.
*	Generate a random configuration and animate until it stabilizes or dies. If it dies, generate a new random configuration.

The source code for this example can be found at:

`installdir\apps\Demo3D\src\com\superscape\m3g\wtksamples\life3d\Life3D.java`.

23.4.2 RetainedMode

The `RetainedMode` MIDlet plays a scene file that shows a skateboarder in an endless loop.

23.4.3 PogoRoo

`PogoRoo` displays a kangaroo bouncing up and down on a pogo stick. To steer the kangaroo, use the arrow keys. Press up to go forward, down to go backward, and left and right to change direction. You might need to hold down the key to see an effect.

24

JSR 180: SIP Communications

The Java ME SDK supports the SIP API for J2ME (JSR 180) with a proxy server, registrar, and network monitor support.

Session Initiation Protocol (SIP) is defined by RFC 3261, available at <http://www.ietf.org/rfc/rfc3261.txt>.

SIP provides a standard way for applications to set up communications. The application determines what communication actually takes place. SIP can be used to set up instant messaging, text chat, voice chat, video conferencing, or other types of sessions.

24.1 Understanding the SIP Registrar and Proxy

A SIP registrar enables client applications to associate a user name with a specific network address. Client registration informs the SIP proxy server that the client exists.

A SIP proxy server is an entry point into a larger network of proxy servers. SIP messages that arrive at one proxy are routed to an appropriate destination, which is usually another proxy server or an end point, such as a desktop computer or a mobile device. Although SIP messages can be sent directly between devices, they are usually routed through a proxy server.

For example, suppose Doug wants to start a video conference with Polly. Polly is on the road and her mobile phone sends a message to a registrar that associates her name with the mobile phone's network address. When Doug tries to set up the video conference with Polly, his application uses SIP to ask the registrar for Polly's current network location.

24.2 Running SIPDemo

This application is a very simple example of using SIP (JSR 180) to communicate directly between two devices. Usually devices will use SIP with a proxy server to set up direct communications of some kind.

To see how SIPDemo works, run two instances of the emulator. In the first, choose Receive message. You can use the default port, 5070, and choose Receive. The first emulator is now listening for incoming messages.

In the second emulator, choose Send message. Fill in values for the recipient, port number, subject, and message, or accept the defaults, and choose Send. Your message will be displayed in the first emulator. The first emulator's response is displayed in the second emulator.

Try it again with the network monitor turned on. You can see the communication between the emulators in the network monitor SIP tab.

JSR 211: Content Handler API (CHAPI)

JSR 211 defines the Content Handler API (CHAPI). The basic concept is that MIDlets can be launched in response to incoming content (files). Modern mobile phones can receive content using SMS, infrared, Bluetooth, e-mail, and other methods. Most content has an associated content type. CHAPI specifies a system by which MIDlets can be launched in response to specific types of content.

See [Section 25.1, "Using Content Handlers"](#) and [Section 25.4, "Running the CHAPIDemo Content Browser"](#).

25.1 Using Content Handlers

In the Java ME SDK Content Handlers are integrated in a project as application descriptors. Content Handlers you define are packaged with the application.

Follow these steps to work with content handlers.

1. In the Projects window, right-click CHAPIDemo and choose Properties from the context menu.
2. In the Category pane, select Application Descriptor, and click the Content Handlers tab.
3. In the Content Handlers table, each line in the list represents the settings for a content handler.


Key	Class	ID	Types	Suffixes
1	example.text.TextViewer	example.text.Te...	text/plain	.txt; .text
2	example.image.ImageViewer	example.image.I...	image/png; image/gif	.png; .gif

- To create a new content handler, press Add, or to edit an existing content handler, press Edit. Both actions open the Content Handler Properties window. See [Section 25.2, "Defining Content Handler Properties"](#).
- To adjust the order of the content handlers, select one and using the Move Up and Move Down buttons. To remove a content handler from the list, select it and press Remove.

- See [Section 25.2, "Defining Content Handler Properties"](#) and [Section 25.4, "Running the CHAPIDemo Content Browser"](#)

25.2 Defining Content Handler Properties

In the Projects window, right-click on a project and choose Properties from the context menu. In the Category pane, select Application Descriptor, and click the Content Handler tab. Pressing Add or Edit opens the Content Handler Properties window.




- In the Class field, choose a class name from the dropdown menu.
- ID is an identification string that can be used to invoke a content handler and control access.
- In Content types, list the content types for which this content handler is responsible. Use Add Type and Remove to manage the list.
- In Suffixes, provide a list of URL suffixes that act as a substitute for an explicit content type.
- In Access allowed to, list IDs for content handlers that are allowed access to this content handler. If the list is empty, access to this content handler is granted to every content handler.

25.3 Defining Content Handler Actions

Content handler actions give invoking applications a choice about how to handle content. An Action is associated with an existing content handler. An image viewer content handler, for example, might include an action for viewing the image at its original size and another action that makes the image fill the available screen space.

In the Projects window, right-click on a project and choose Properties from the context menu. In the Category pane, select Application Descriptor, and click the Content Handler tab. Press Add or Edit to open the Content Handler Properties window and click on the Actions tab, as shown here.



The Actions list contains the internal names of the actions for this content handler. Locales is a list of all the locales for which human-readable action names will be provided. Localized actions is a grid which contains the human-readable action names for various locales. Each locale is represented by a row, while the actions are listed as columns. You can see all the human-readable action names for a particular locale by reading across a single row.

25.4 Running the CHAPIDemo Content Browser

This demo is a content browser that takes advantage of the content handler registry. It allows you to view different types of content from different sources.

1. In the user interface, select File > Open Sample Project > CHAPIDemo.

In the device selector, right-click on a device, select Run Project OTA, and choose CHAPIDemo.

- You are asked to enter the password for the keystore. Type: `keystorepwd`
- You are asked to enter the password for the "dummyca" key pair alias within the keystore. Type: `keypwd`
- On the Favorite Links page, choose CHAPI Demo. Press the menu soft button and choose 1, Go.

The Text Viewer displays a Media Player URL and links to various media files.

2. Select `Duke.png`. Use the arrows to highlight the link, then select the file. Using CHAPI, the ImageViewer MIDlet runs and displays the Duke image. Select the Back soft key to return to the Text Viewer.
3. Install the Media Player to view media.
 - Select the URL `http://handlers/MediaHandler.jad`.
Select the Menu soft button and select item 1, Go.
 - The application asks, "Are you sure you want to install Media Handler?" Select the Install soft key. For the rest of this demo, click Install if you are asked for confirmation.

The installation finishes and you return to the Text Viewer.
4. View different media files.
Select a URL from the list, select the Menu soft button and select item 1, Go.

JSR 226: Scalable 2D Vector Graphics

JSR 226, Scalable 2D Vector Graphics for J2ME, supports rendering sophisticated and interactive 2D content.

Scalable Vector Graphics (SVG) is a standard defined by the World Wide Web Consortium. It is an XML grammar for describing rich, interactive 2D graphics.

The Scalable Vector Graphics (SVG) 1.1 specification (available at <http://www.w3.org/TR/SVG11/>) defines a language for describing two-dimensional graphics in XML.

SVG Tiny (SVGT) is a subset of SVG that is appropriate for small devices such as mobile phones. See <http://www.w3.org/TR/SVGMobile/>. SVGT is a compact, yet powerful, XML format for describing rich, interactive, and animated 2D content. Graphical elements can be logically grouped and identified by the SVG markup.

Java ME applications using SVG content can create graphical effects that adapt to the display resolution and form factor of the user's display.

SVG images can be animated in two ways. One is to use declarative animation, as illustrated in [Section 26.1.3, "Play SVG Animation"](#). The other is to repeatedly modify the SVG image parameters (such as color or position), through API calls.

While it is possible to produce SVG content with a text editor, most people prefer to use an authoring tool. Here are two possibilities:

- **Ikivo Animator:** <http://www.ikivo.com/animator/>
- **Adobe Illustrator:** <http://www.adobe.com/products/illustrator/main.html>

26.1 Running SVGDemo

This project contains MIDlets that demonstrate different ways to load manipulate, render, and play SVG content.

26.1.1 SVG Browser

The SVGBrowser MIDlet displays SVG files residing in the phone file system. Before running this demo, place an SVG file in your device skin's file structure at:

device\appdb\filesystem\root1

For your device location, see [Section 8.4, "Java ME SDK User Directories"](#) and [Table 8-1](#). Launch the demo. The application displays the contents of *root1*. Select your SVG file and choose the Open soft key.

26.1.2 Render SVG Image

Render SVG Image loads an SVG image from a file and renders it. Looking at the demo code you can see that the image is sized on the fly to exactly fit the display area. The output is clear and sharp.

26.1.3 Play SVG Animation

This application plays an SVG animation depicting a Halloween greeting card. Press 8 to pause, 5 to start or resume, and 0 to stop.

The SVG file contains a description of how the various image elements evolve over time to provide this short animation.

In the following code sample, the JSR 226 `javax.microedition.m2g.SVGImage` class is used to load the SVG resource. Then, the `javax.microedition.m2g.SVGAnimator` class can take all the complexity of SVG animations and provides a `java.awt.Component` or `javax.swing.JComponent` which plays the animation. The `SVGAnimator` class provides methods to play, pause and stop the animation.

```
import javax.microedition.m2g.ScalableGraphics;
import javax.microedition.m2g.SVGImage;

...
String svgURI = ...;
SVGImage svgImage = (SVGImage) SVGImage.createImage(svgURI, null);
SVGAnimator svgAnimator = SVGAnimator.createAnimator(svgImage);

// If running a JSE applet, the target component is a JComponent.
JComponent svgAnimationComponent = (JComponent) svgAnimator.getTargetComponent();
...

svgAnimator.play();
...
svgAnimator.pause();
...
svgAnimator.stop();
```

26.1.4 Create SVG Image from Scratch

This demo builds an image using API calls. It creates an empty `SVGImage`, populates it with a graphical content, and then displays that content.

26.1.5 Bouncing Balls

Bouncing Balls plays an SVG animation. Press 8 to play, 5 to start, and 0 to stop. If you press 8, pressing 5 resumes the animation. If you press 0, pressing 5 starts the animation from the beginning.

26.1.6 Optimized Menu

In this demo, selected icons have a yellow border. As you move to a new icon, it becomes selected and the previous icon flips to the unselected state. If you navigate off the icon grid, selection loops around. That is, if the last icon in a row is selected, moving right selects the first icon in the same row.

This demo illustrates the flexibility that combining UI markup and Java offers: a rich set of functionality (graphics, animations, high-end 2D rendering) and flexibility in graphic manipulation, pre-rendering or playing.

In this example, a graphic artist delivered an SVG animation defining the transition state for the menu icons, from the unselected state to the selected state. The program renders each icon's animation sequence separately into off-screen buffers (for faster rendering later on), using the JSR 226 API.

With buffering, the MIDlet is able to adapt to the device display resolution (because the graphics are defined in SVG format) and still retain the speed of bitmap rendering. In addition, the MIDlet is still leveraging the SVG animation capabilities.

The task of defining the look of the menu items and their animation effect (the job of the graphic artist and designer) is cleanly separated from the task of displaying the menu and starting actions based on menu selection (the job of the developer). The two can vary independently as long as both the artist and the developer observe the SVG document structure conventions.

26.1.7 Picture Decorator

In this sample you use the phone keys to add decorations to a photograph. The key values are:

Key	Action
1	key shrink
2	key next picture
3	key grow
4	key help
5	key horizontal flip
6	key vertical flip
7	key rotate counter-clockwise
8	key previous picture
9	key rotate clockwise
#	display picker options

This demo provides 16 pictures for you to decorate.

Use the 2 and 8 keys to page forward and back through the photos.

To decorate, press # to display the picker. Use the arrow keys to highlight a graphic object. The highlighted object is enlarged. Press Select to choose the current graphic or press the arrow keys to highlight a different graphic. Press Select again to add the graphic to the photo. When the decoration is added you see a red + on the graphic. This means it is selected and can be moved, resized, and manipulated.



Use the navigation arrows to move the graphic. Use 1 to shrink the graphic, and 3 to enlarge the graphic. Use 5 or 6 to flip, and 7 or 9 to rotate. When you are satisfied with the position, press Select. Note that a green triangle appears. This is a cursor. Use the navigation keys to move the green triangle around the picture. When the cursor is over an object it is highlighted with a red box. Press Select. The red + indicates the object is selected.



To remove a decoration (a property), select an object, then click the Menu soft key. Press 2 to remove a property.

26.1.8 Location Based Service

Launch the application. A splash screen (also used as the help) appears. The initial view is a map of your itinerary - a walk through San Francisco. The bay (in blue) is on the right of your screen. Press 1 to start following the itinerary. The application zooms in on your location on the map. Turn-by-turn directions appear in white boxes on the horizontal axis. While the itinerary is running, Press 7 to rotate the map counter-clockwise. Note, the map rotates and the text now appears on the vertical axis. Press 7 again to restore the default orientation. Press 4 to display the help screen.




26.1.9 Running SVGContactList

This application uses different skins to display the same contact list information and a news banner. The skins have different colors and fonts.

Select `SVGContactlist(skin 1)` or `SVGContactlist(skin 2)`, then click Launch.

Use the up and down arrows to navigate the list of contacts. The highlighted name is marked with a special character (a > or a dot) and is displayed in a larger font.



Press the select button to see more information for the highlighted name.



Press select again to return to the contact list.

JSR 229: Payment API Support

JSR 229, the Payment API, enables applications to make payments on behalf of their users. The Payment API supports different payment mechanisms through payment *adapters*. A device that implements the Payment API has one or more adapters. MIDlet suites use descriptor attributes to specify what types of payment adapters they can use.

The Java ME SDK implements the Payment API with a sample payment adapter that simulates both Premium Priced SMS (PPSMS) and credit card payments. In addition, the SDK makes it easy to set the necessary attributes in the MIDlet's descriptor and JAR file manifest. Finally, a payment console enables you to easily track payments made or attempted by an application.

Because the Payment API is closely tied to provisioning and external device payment mechanisms, and because payments can only succeed in a trusted protection domain, always test and debug your Payment API applications using the Run via OTA feature.

- [Section 27.1, "Running the Payment Console"](#)
- [Section 27.2, "Running JBricks"](#)

27.1 Running the Payment Console

The Payment Console is a simple monitoring tool that displays payment related transactions sent from a mobile application using the Payment API (JSR 229). The payment console monitors Payment Update File requests and Premium Priced SMS payments.

The Payment Console is implemented as an Http server running within the Device Manager process. The root for the Http server is *installdir\apps*.

Note: The Device Manager must be running before you launch the Payment Console.

To launch the Payment Console in NetBeans, select Windows > Output > Payment Console. The console opens as a window at the bottom of the IDE.

The initial message is:

```
Payment Console is running
using phone number 5550000
listening on http://localhost:54465
```

You can also launch the Payment console from the command line:

installdir\bin\payment-console.exe

To close the Payment Console launched from the command line, press Enter.

To change the Payment Console Phone number, go to the Device Selector and right-click the platform node (CDC or CLDC). Reset the Payment Console Phone Number property from the platform Properties window.

27.2 Running JBricks

JBricks is a game that demonstrates the use of the JSR 229 Payment API. The game itself resembles Breakout or Arkanoid. In JBricks, you can buy another life or a new game level. Behind the scenes, the Payment API handles the details.

1. Right-click the JBricks project and select Properties from the context menu.
2. Select the Running Category and choose the Execute through OTA radio button. Click OK.
3. Run the JBricks demo. The first time you run the game it will be installed over the air. If the game is already installed, select JBricks from the AMS, and wait for the game home page to load (you see a list of actions where the first item is Start Game).

On the game home page, select the level if necessary, then select Start Game and click again to begin the round.

4. Use the left and right arrow keys to move the paddle to keep the bar from hitting a wall.

To see how JBricks uses the Payment API, choose either Buy Life or Buy Level from the game's main menu. Next, choose whether you want to buy a single life or three lives for a lower bulk price.


When you choose the Buy transaction you are asked to confirm the Premium Priced SMS carrier. The JBricks demo supports three different carriers. To change carriers, set the Payment properties for the device running the demo. In the Device Selector, right-click the device and select Properties. You can set the payment property values as follows to change the carrier:

SONERA: MCC=999, MNC=99

DNSDNA: MCC=380, MNC=77

RADIOG: MCC=747, MNC=88

To view your transactions in the emulator, select Device > Payment Transactions tab. Transactions for this specific instance of the emulator are displayed.



In addition, you can view all transactions passing through the SDK's payment system. Choose Windows > Output > Payment Console. A transaction in the console looks something like the following:

```

PSP Console running, using phone number +5550001.
PSP Server running at https://localhost:-1
Received Payment Request from 127.0.0.1
    Credit card issued by: VISA
    Credit Card type: 0
    Credit Card Number: 4111111111111111
    Credit Card Holder: Jonathan Knudsen
    Feature ID: 3_lives
    Credit Card Verification Number (CCV): 123
    Payload: null
    Response to 127.0.0.1
    HTTP/1.1 200 OK
    Content-Length: 0
    Pay-Response: SUCCESSFUL
    Pay-Timestamp: 1156282954734
  
```

JSR 238: Mobile Internationalization API (MIA)

JSR 238, the Mobile Internationalization API, is designed for applications that are to be displayed in multiple languages and used in multiple countries. The combination of country (or region) and language is a *locale*.

The central concept of JSR 238 is a *resource*, which is a string, image, or other object that is suitable for a particular locale. For example, an application that is to be distributed in Europe might include resources for Italian-speaking people living in Italy, Italian-speaking people living in Switzerland, Spanish-speaking people living in Spain and so on.

Resources are stored in files in a format defined in JSR 238. The resource files are bundled as part of the MIDlet suite JAR file. The Java ME SDK provides a resource manager that simplifies the job of creating and maintaining resource files.

28.1 Setting the Emulator's Locale

Alternatively, while the emulator is running, select Application > Change Locale and type in the locale you want to use.

You can change an emulator's locale from the Device Selector.

1. Right-click on a device and choose Properties.
2. In the Properties window, find the Locale property and click ... to open the Locale window.
3. Select the locale from the dropdown list.

28.2 Using the Resource Manager

To launch the resource manager, select a project, then choose Tools > Internationalization > Java ME Internationalization Resources Manager.

All the resources for the selected project are displayed in the Resource Manager. See the sample project i18nDemo described in [Section 28.3, "Running i18nDemo"](#).

See also: [Section 28.2.1, "Working With Locales"](#) and [Section 28.2.2, "Working With Resource Files"](#).

28.2.1 Working With Locales

Locales are represented as folders under the top-level `global` node. The locale directories contain resource files which, in turn, hold the actual resources that can be used by the application.

Locales are represented by standard language and country codes as described in the MIDP 2.0 specification. For example, `pt-BR` represents Portuguese-speaking people living in Brazil.

- To add a locale, right-click on the top-level `global` node and choose Add Locale. Choose the locale from the combo box, or type it directly, and click OK.
- To rename a locale, right-click the locale directory and choose Rename.
- To remove a locale and all its contained resource files, right-click the locale directory and choose Delete.

28.2.2 Working With Resource Files


Resource files can be global (at the top level) or specific to a locale.

- To create a new global resource file, right-click the top-level `global` directory and choose Add new resource file. Choose a name for the file.
- To rename a resource file, right-click the file and choose Rename.
- You can copy, cut, and paste entire resource files. Right-click a file and choose Copy or Cut. Then right-click the locale directory (or the top-level `global`) and choose Paste.
- To remove a resource file, right-click the file and choose Delete.

28.2.3 Working With Resources

Click on a resource file to display its contents.

- To add an image or another type of binary data, click the Add button.
 - In the Configure New Resource window, select Add string resource.
 - Browse to select the file you want to add.
 - The automatically supplied Identifier value can be changed.
 - Click OK to add the resource.



- To edit a resource, double-click in the resource field.
 - For strings you can edit an existing value.
 - Double-clicking a binary file opens a file chooser.

28.3 Running i18nDemo

This MIDlet suite demonstrates the JSR 238 Mobile Internationalization API. The MIDlets String Comparator and Formatter show how to sort strings and display numbers appropriately for different locales. The third MIDlet, MicroLexicon, is a small phrase translator that comes in handy if you need to ask for a beer in Prague, Herzliya, Beijing, Milan, or several other locations.

Note: The default fonts for the Java ME SDK do not support Chinese and Japanese. To use these languages, follow these steps before running this demo: 1. Install a True Type font that supports Chinese or Japanese. 2. Modify `installdir\toolkit-lib\devices\skin-directory\conf\skin.properties` to specify that font.

To run a MIDlet, highlight the MIDlet, then use the Launch soft button to run the MIDlet.

String Comparator

The String Comparator MIDlet demonstrates how strings (city names) are sorted differently depending on locale. Launch the MIDlet. Use the Menu soft button to view the menu. Click or Type 2 to select Sort - default, and the list is sorted alphabetically. Click or Type 3 to select Sort - slovak. It's easy to see the difference in the cities that begin with the letter Z, with and without the mark on top. Click Exit to return to the list of MIDlets.

Formatter

The second MIDlet, Formatter, simply displays times and numbers formatted for different locales. Click next to view all four screens. Click Exit to return to the list of MIDlets.

MicroLexicon


The final MIDlet, MicroLexicon, translates phrases from one language to another language. To set the source language, follow the steps in [Section 28.1, "Setting the Emulator's Locale"](#).

To select the target language from the list, use the navigation arrows to highlight Choose Language. Click the Select button to view the language drop down. Use the navigation arrows to choose a language and then click Select. Click the Next soft button.

MicroLexicon displays a list of phrases. Highlight one and press the Select button on the emulator.

MicroLexicon displays the flag of the target language and the translated phrase.

MicroLexicon is powered by MIDlet resources. To understand how you can use the Java ME SDK to localize an application, choose Tools > Internationalization > Java ME Internationalization Resources Manager. All the resources, both text and images, used by MicroLexicon, appear. You can edit the resources and run MicroLexicon again to see what happens.



id	resource
1	MicroLexicon lets you easily translate usefu...
2	MicroLexicon & co.
3	Choose language
4	Choose phrase
5	Translated phrase
101	
102	
103	
104	
105	
106	
107	
108	
109	
201	english
202	czech
203	slovak
204	hebrew
205	chinese
206	japanese
207	german
208	italian
209	spanish
110	No more beer

To practice creating and editing resources, see [Section 28.2.2, "Working With Resource Files"](#).

The resources are stored in the project's JAR file.

JSR 239: Java Bindings for OpenGL ES

JSR 239 provides a Java language interface to the open standard OpenGL ES graphics API.

29.1 OpenGL Overview

JSR 239 defines the Java programming language bindings for two APIs, OpenGL for Embedded Systems (OpenGL ES) and EGL. OpenGL ES is a standard API for 3D graphics, a subset of OpenGL, which is pervasive on desktop computers. EGL is a standard platform interface layer. Both OpenGL ES and EGL are developed by the Khronos Group <http://khronos.org/opengles/>.

While JSR 184 (which is object oriented) requires high level functionality, OpenGL is a low-level graphics library that is suited for accessing hardware accelerated 3D graphics.

Explore the OpenGL ES Demo sample project code.

JSR 256: Mobile Sensor API Support

The JSR 256 Mobile Sensor API allows Java ME application developers to fetch data from sensors. A sensor is any measurement data source. Sensors can vary from physical sensors such as magnetometers and accelerometers to virtual sensors that combine and manipulate the data they have received from various kinds of physical sensors. An example of a virtual sensor might be a level sensor indicating the remaining charge in a battery or a field intensity sensor that measures the reception level of the mobile network signal in a mobile phone.

JSR 256 supports many different types of sensor connection (wired, wireless, embedded and more) but this SDK release only provides preconfigured support for sensors embedded in the device.

The SDK GUI provides sensor simulation. The emulator's External Events Generator Sensors tab allows you to run a script that simulates sensor data.

You can use the custom API available with the SDK to create a custom sensor implementation with additional capabilities and support for different connection types.

The Sensors demonstration has two MIDlets, SensorBrowser and Marbles that demonstrate the SDK's implementation of the Mobile Sensor API. Use the Run via OTA feature to install the application into the emulator.

30.1 Creating a Mobile Sensor Project

To use this API, create a project with the target platform Custom. You must select MIDP 2.0 or higher and CLDC 1.1 before you can select the Mobile Sensor API optional package.

To set permissions, click the Settings button and choose the Permissions icon.

A sensor project freely detects sensors, but this does not imply you can get data from the sensors you find. You might need to explicitly set permissions in your project so you can interact with certain sensors.

The following permissions work with the preconfigured embedded sensors shipped with the SDK:

- `javax.microedition.io.Connector.sensor`
Required to open a sensor connection and start measuring data.
- `javax.microedition.sensor.ProtectedSensor`
Required to access a protected sensor.
- `javax.microedition.sensor.PrivateSensor`

Required to access a private sensor.

A sensor is private or protected if the sensor's security property has the value private or protected. The security property is an example of a sensor property you might create for yourself in your own sensor configuration. You can create your own optional properties using `com.sun.javame.sensorN.proplist` and `com.sun.javame.sensorN.prop.any_name`, where *N* is the sensor number and *any_name* is the name of your property. The security sensor property was created as follows:

```
# add security into proplist
com.sun.javame.sensor<N>.proplist: security
# add security property value
com.sun.javame.sensor<N>.prop.security: private
```

30.2 Using a Mobile Sensor Project

A Sensor project can be installed over the air. In the emulator window, select Device > Sensors. In this tab you can view all sensors currently available in the emulator, with the sensor ID, name, and availability. If the sensor supports change to availability you can click on the check box to change it. As mentioned earlier, the provided implementation does not support availability change, but a custom implementation you create might do so.

When you select a sensor row the bottom of the dialog displays any custom sensor controls. For example, the acceleration sensor, has three channels: `axis_x`, `axis_y`, and `axis_z`. Each channel has a slider that changes the current channel value, and an edit box you can use to input a value. The channel unit label is displayed on the far right.

Under the channels there is script player control that allows you to play sensor value events from a script file of the format discussed in [Section 30.3, "Creating a Sensor Script File"](#). See [Section 30.4, "SensorBrowser"](#) for a description of how to use the Sensors demo.

30.3 Creating a Sensor Script File

To simulate sensor inputs, provide a sensor script. The file format is as follows:

```
<sensors>
  <value time="0">
    <channel id="0" value="0" />
    <channel id="1" value="0" />
  </value>
  <value time="100">
    <sensor active="false"/>
  </value>
  <value time="100">
    <channel id="0" value="-50" />
    <channel id="1" value="10" />
    <sensor active="true"/>
  </value>
</sensors>
```

The file `installdir\apps\Sensors\marbles.xml` is an example of a sensor script file. The attributes are as follows:


- The attribute time in the value tag is the delay from the previous command in milliseconds.
- The channel tag sets the value of the channel with the specified id value, to value. The channel ignores the id if the value of id is not specified or if the value is out of the channel range.
- The sensor tag is a true or false value that makes the sensor available or unavailable. The pre-configured sensors provided with this release are embedded, so they cannot be deactivated. If you configure your own sensor that is not embedded, it will be possible to deactivate it.

30.4 SensorBrowser

The SensorBrowser application displays the sensor detail information for each channel defined for the demo.

1. In the emulator select SensorBrowser and use the soft key to select Launch the application.
The emulator displays a list of sensors.
2. Use the navigation keys to highlight a sensor, then use the soft key to select Detail.

For example, the following screen shows the details for the acceleration sensor.



Click Back, then click Exit to return to the application menu.

30.5 Marbles

This demonstration uses the Marbles game to provide visual feedback for sensor inputs provided in a script.

1. From the application menu select Marbles and use the soft key to launch the application.
2. In the emulator, select Device > Sensors.

The emulator displays a list of the sensors in this application.

3. Click the Browse button and choose the following file:
installdir\apps\Sensors\marbles.xml.
4. Observe the movement of the marbles on the emulator screen. On the external events screen you can see the sliders move as the script runs. You can use the familiar controls to play, pause, and stop the script.

31

JSR 253: Mobile Telephony API

The Mobile Telephony API (MTA) specification

(<http://www.jcp.org/en/jsr/summary?id=253>) defines a set of functions for controlling voice calls and using network services. Because the MTA is optimized for small devices with limited memory and processing power, these functions are effective for Java ME applications written for many devices.

31.1 The MTA Implementation

Although JSR 253 can be based on any available telephony protocol, the specification describes only the GSM, UMTS and CDMA protocols. The OJWC implementation provides the ability to add support of any protocol. For details on the implementation, see the *Oracle® Java Wireless Client Porting Guide* at

<http://download.oracle.com/javame/config/cldc/cldc-opt-impl/ojwc-3.0>.

In the Java ME SDK the reference implementation is only able to receive external MTA events generated by the Mobile Telephony panel. In the SDK, launch an emulator and select Device > Mobile Telephony. The controls on this external events generator tab are reserved for TCK testing.

The Java ME SDK integrates a server and other infrastructure so that you can exchange MTA events between emulators without using the external events generator. See [Section 31.2, "Running the MtaDemo"](#).

31.2 Running the MtaDemo


This sample project demonstrates how the Java ME SDK MTA features can be used to simulate telephony actions. JSR 253 does not address presentation issues and UI issues. The behaviors described here are those of the sample application. Also, this sample focuses on call functionality and call state changes. It has no audio capability.

Note: In this simulation, when the caller terminates a connection the destination device connection is not terminated automatically. Both the caller and the call recipient must manually terminate the connection. This is necessary because of a bug in the OJWC implementation.

1. In the Projects tab, Right-click MtaDemo and select Run With... and select DefaultClcdPhone1 (Device 6) from the dropdown menu.

Repeat this process to launch MtaDemo on DefaultClcdPhone2 and DefaultClcdPhone3 (Devices 7 and 8, respectively).

2. In each emulator, select the MtaDemo MIDlet to install the application. The initial screen shows this control




3. From the Device 6 emulator place a call to Device 7. Type 123456790 in the Phone field, and press Connect.
4. The Device 7 emulator displays a notification to accept or reject the call. Press the Accept soft button.

The Active sessions dropdown is shown on Devices 6 and 7. The active session is shown in bold font.

Note the state change and address are recorded in the Output window for both emulator sessions.

5. From Device 8 place a call to Device 7.
6. The Device 7 emulator displays a prompt to accept or reject the call. Press the Accept soft button.

The initial call is automatically set on hold. The held connection is shown in italics in the Active sessions dropdown.



7. On Device 7, select the active session from device 8 (123456791) and from the soft Menu, choose Terminate.
8. On Device 8, terminate the active session.
9. On Device 7, choose the held active session (123456790) and from the soft Menu, select Set on Active.

This covers the basic transactions in the MtaDemo. At this point you can manually put a call on hold by choosing Set on Hold, and then initiate a call to a device that has no active sessions. If the device has an active session, you will see the error "Maximum number of active calls reached" in the emulator and in the output window.

JSR 257: Contactless Communication API

The Contactless Communication API (<http://jcp.org/en/jsr/detail?id=257>) is a Java ME optional package that allows applications to access information on contactless targets, such as Radio Frequency Identification (RFID) tags and bar codes. RFID tags are often used in business for item identification, article surveillance, and inventory. Each RFID contains a unique identification number used to identify a tagged object.

Using the JSR 257 API, an RFID reader can be built into a Java Wireless Client software phone stack, allowing the handset to read data from a tagged target and write data back to it. RFID readers use the 13.56 MHz radio frequency and the communication distance is usually less than 10 centimeters.

The Near Field Communication (NFC) Forum defines the NFC Data Exchange Format (NDEF) data packaging format. NDEF facilitates communication with an RFID tag, or between one NFC device and another. The Contactless Communication API provides a connection to any physical target that supports the NDEF standard, allowing applications to exchange data with any target tagged with NDEF formatting, regardless of actual physical type.

For an explanation of this implementation, see the *Oracle Java Wireless Client Porting Guide*.

32.1 Using ContactlessDemo

The Java ME SDK provides a way to test contactless communication. The MIDlet running on the emulator waits to detect an RFID tag. You can simulate the tag communication using the emulator's external events generator to detect and attach the tag. You can use one of the tags included in the sample, or create tag files of your own, as described in [Section 32.2, "Tag File Formats"](#).

1. Launch the ContactlessDemo. The MIDlet notifies you that it is waiting for a tag.
2. In the emulator, choose Device > Contactless Communication. In the external events generator the tag emulator supplies three tags by default: hello, nested, and vcard.
3. To test the connection, select an available tag and press the Attach tag button.

In the emulator the MIDlet notifies you that the NDEF target is detected, displays the tag information, and prints the payload if it is a text record.

In the external events generator, press the Detach tag button to end the session.

Events are recorded in the log area. To clear the log, right-click and select delete text. To clear the emulator screen press the Clear soft button.

4. To create your own tag, create a tag file according to the NFC Data Exchange Format (NDEF). For a sample, see [Section 32.2, "Tag File Formats"](#).

In the external events generator, press the Create tag button, browse to select your tag file, and press Open. If the file is properly formed, the new tag is added to the available tags list.

You can use the Remove tag button to remove any tag from the list. If it's a tag you created, the original file on disk is not affected. If the default tags are removed, they will reappear when you restart the demo.

5. Optional. Instead of performing interactive actions in the external events generator, you can use a script to do the same thing.

Create a file as directed in [Section 32.3, "Script Format"](#). In the external events generator, click the Browse button to locate your script, then press Play.

32.2 Tag File Formats

Tags are created in XML format in accordance with the NFC and NDEF standards. To see how the sample files are formed, see:

installdir\toolkit-lib\modules\emulator-ui-window-external-events\jsr257\conf\tags.

A sample file with several records might look like this:

```
<?xml version="1.0" encoding="UTF-8"?>
<jsr257client>
    <UID>12-CD-45-67-89-AB-CD</UID>
    <TargetProperties>
        <TargetProperty>NDEF</TargetProperty>
    </TargetProperties>
    <NDEFMessage>
        <NDEFRecord>
            <Format>MIME</Format>
            <Name>text/example</Name>
            <Id>urn:company:product:ndef:payload:3</Id>
            <Payload>payload</Payload>
        </NDEFRecord>
        <NDEFRecord>
            <Format>MIME</Format>
            <Name>text/plain</Name>
            <Id>mimeid</Id>
            <Payload>Hello, MIME World!</Payload>
        </NDEFRecord>
        <NDEFRecord>
            <Format>URI</Format>
            <Name>http://www.oracle.com/technetwork/java/javame/index.html</Name>
            <Id>jme</Id>
            <Payload>Java ME</Payload>
        </NDEFRecord>
        <NDEFRecord>
            <Format>NFC_FORUM_RTD</Format>
            <Name>urn:nfc:wkt:Sp</Name>
            <Id></Id>
            <Payload>smart-poster</Payload>
        </NDEFRecord>
        <NDEFRecord>
            <Format>MIME</Format>
            <Name>text/x-vCard</Name>
            <Id>duke</Id>
```

```
<Payload>BEGIN:VCARD VERSION:2.1 FN:Oracle TEL:+1-650-506-7000
ADR:500 Oracle Parkway;City: Redwood Shores;
State: CA;94065 END:VCARD
</Payload>
</NDEFRecord>
</NDEFMessage>
</jsr257client>
```

32.3 Script Format

You can use the external events generator buttons to attach and detach a tag, or you can write a script to perform these actions. The script syntax is as follows:

```
# Comment:
# this is a comment
# Tag definition:
tag <tag name> <path to the tag xml file>
# Attach tag:
attach <tag name>
# Delay. Ensures the tag is attached before other actions.
wait <time in ms>
# Print tag information:
print <tag name>
# Detach tag:
detach <tag name>
```

This is a sample script:

```
tag C D:\MyTags\ccomtag.xml
attach C
print C
wait 10000
detach C
```

JSR 258: Mobile User Interface Customization API

JSR 258 (<http://jcp.org/en/jsr/detail?id=258>) defines a standardized Java ME API for querying and manipulating themes and skins on a device. It also defines a file format for describing theme and skin data.

As specified in the JSR, you can define the theme (the appearance) in an XML file with local references to resource files (images, sounds and more) or it can be a JAR file that contains the XML file, its resources, and a properly defined manifest file.

You can use named colors or color values expressed in ARGB format.

- Named colors must be recognized color keywords as found in the SVG 1.1 specification. See:
<http://www.w3.org/TR/SVG/types.html#ColorKeywords>
- Color values must be a numeric constant in the form #AARRGGBB, where the components RR, GG and BB are 8-bit values expressed as hexadecimal constants. AA is the opacity level, FF being fully opaque, and 00 fully transparent. For example, the ARGB value for white is #FFFFFF. See JSR 258 for a full explanation.

33.1 Running the Customization Sample Project

This MIDlet is a color converter that can be viewed using one of three appearances. The converter accepts a hexadecimal, decimal, or octal color specification and converts it to RGB format.

Follow these steps to run the demo:

1. Select a theme from the radio button list and press the Demo soft key.
2. Choose a system and enter a value in that format in the Enter Color field. The Alpha value is optional.

From the soft menu, choose option2, Process. The color converter displays the RGB value.

33.2 Revising Sample Project Appearances

Appearances are associated with the device, in this case, the emulator. To see the XML files for this sample, go to the working directory for the current emulator. For example, see:

C:\Documents and Settings\user\javame-sdk\3.0.5\work\device#\appdb\customization

The demo allows you to override these sample themes.

1. Make a copy of a theme file and store it in a different directory.

The sample expects the file names `theme_green.xml` and `theme_red.xml`. When a theme is revised it is overwritten in the emulator's working directory, so your edited copy must reside elsewhere.

2. Experiment with changing color values, fonts, or other settings, and save your changes. As mentioned earlier, color values must be specified in ARGB format, or you can use an SVG 1.1 color keyword.
3. Run the demo, and in the emulator, choose Device > Customization. The external events generator opens with the Customization tab selected.
4. In the Appearances area, select the theme you have edited and press the Deinstall button. This does not delete the theme, it merely unloads it from this session.
5. Press the Install button and browse to select your edited theme. Installing overwrites the theme in the emulator's working directory.
6. Close the emulator.
7. Run the Customization project, and choose the revised theme. Verify that your changes are visible.
8. To restore the original themes, run the project and in the emulator, choose Device > Customization. Press Reset. This overwrites the current themes with the project's original themes.

Index

A

AMS, 4-2
appearances, 33-1
application versioning, 5-1

B

Bluetooth, 17-1
building (command line), 13-5

C

CBS message, sending, 22-2
CDC stack, 2-2
certificate management, 12-6
-classpathoption, 13-6
CLDC and MIDP stack, 2-1
command line operations, 13-1
command path, 13-5
Common Name, 12-5
Contactless Communication API, 32-1
content handler, 25-1
 actions, 25-3
 properties, 25-2
cref, 20-2

D

data.prof, 8-3
debugging
 from command line, 13-4
 options, 13-4
demonstration applications, 3-3
device
 information, 6-2
device manager, 2-1, 13-1

E

emulation platform, 2-1
emulator, 2-1, 6-1
 default protection domain, 13-7
 skins, 6-1
emulator phone number, 22-2
emulator proxy server, 3-2

F

FileConnection API, 16-1
Files window, 4-7
font size, 1-1

G

generating stub from command line, 13-9

H

heap size, 6-2, 7-3
-help option, 13-2
hex view, 10-2

I

immediate mode, 23-1
-import command, 13-9

J

J2ME Web Services Specification, 19-1
JAD file, 4-1
 creating, 5-7
JadTool, 13-7
JAR file, 4-1
 add, 5-6
 creating and compressing, 5-7
Java Cryptography Extension (JCE) keystore, 13-8
javame-sdk, 8-3
JCP, 15-1
JSR, 15-1
JSR 118, 12-1
JSR 120, 22-1
JSR 135, 18-1
JSR 172, 19-1, 19-2
JSR 177, 20-1
JSR 179, 21-1, 21-3
JSR 180, 24-1
JSR 184, 23-1, 23-2
JSR 185, 12-1
JSR 205, 22-1
JSR 211, 25-4
JSR 229, 27-1, 27-2
JSR 238, 28-1, 28-3

JSR 239, 29-1
JSR 248, 12-1
JSR 253, 31-1
JSR 257, 32-1
JSR 258, 33-1
JSR 75, 16-1, 16-2, 16-3
JSR 82, 17-1, 17-2
JTWI security domains, 12-2

K

key
 exporting, 5-8
key management, 12-3
key pair
 alias, 12-5
 creating, 12-5
 importing, 12-5
keystore, JCE, 13-8
keystore.ks, 3-6
keytool utility, 13-8

L

locale, 6-3
Location API, 21-1
logical view, 4-6
LWUIT, 11-1

M

M3G, 23-1
managing certificates from command line, 13-8
manifest file, 13-6
MEKeyTool, 13-8
messages tree sorting, 10-2
method profiling, 9-1
MIA, 28-1
MMAPI, 18-1, 18-4
Mobile 3D Graphics API, 23-1
Mobile Internationalization API, 28-1
Mobile Media API, 18-1
Mobile Media API (MMAPI), 18-1
 capture, 18-2
Mobile User Interface Customization API, 33-1
multiple user environment, 8-1

N

NDEF, 32-1
network monitor
 filtering, 10-2
 sorting messages, 10-2
NFC, 32-1

O

OBEX, 17-1
obfuscate project, 5-7
OpenGL ES, 29-1
Organization Name, 12-5

Organization Unit, 12-5

P

packaging, 5-7
packaging using command line, 13-6
Payment API, 27-1, 27-2
PDA Optional Packages, 16-1
PDAP, 16-1
permissions, 12-2
Personal Information Management (PIM) API, 16-1
phone number, 6-2
phoneME, 2-1
physical view, 4-7
PIM API, 16-2
preverifying, 13-5
 example from command line, 13-6
profiler, 9-1, 13-4
project, 4-1
 add, 5-6
 build, 4-6
 clean, 4-6
 close, 4-6
 import, 4-8
 new, 4-6
 run, 4-6
 set as main, 4-6
Projects window, 4-6
properties
 device, 6-2
 enable profiler, 9-2
 platform, 6-2
 searchable in WURFL, 7-2
protection domains, 12-1
proxy server, 3-2

R

reference problem, 3-6
resolve reference problems, 3-6
resources, 4-7
retained mode, 23-1
RFID, 32-1
ring tones, 18-2
roots in the FileConnection API, 16-1
run options, 13-2
Run via OTA, 12-2

S

SATSA, 20-1
SATSA demos, 20-6
Scalable 2D Vector Graphics API, 26-1
scene graph, 23-1
SDK, running from command line, 13-1
serial port, 6-3
settings, 1-2, 4-1
signed MIDlet suites, 12-1
signing MIDlet suites, 12-3, 13-7
SIP API, 24-1
SMS text message, sending, 22-2

source packages, 4-7
stub generator for web services, 19-1
SVG, 26-1
SVGDemo, 26-1
SVGT, 26-1
switch users, 8-1

T

toolbar, running from the command line, 13-1

U

UEL, 8-1
update center, 1-3
user switching, 8-1
userhome, 8-3
utilities, 1-2

V

-version option, 13-2
versioning applications, 5-1

W

Web Services specification, 19-1
web services, stub generator, 19-1
Wireless Messaging API, 22-1
WMA, 22-1
WMA console, 22-1
wscompile, 13-9
WURFL, 7-1
WURFL search, 7-1
WURFL search filter, 7-2

X

-Xdebug option, 13-4
-Xrunjdwp option, 13-4

