

Oracle® Java Micro Edition Software Development Kit

Developer's Guide

Release 3.4 for NetBeans on Windows

E24265-06

September 2013

This document describes how to use the Oracle Java ME SDK plugin for NetBeans.

Oracle Java Micro Edition Software Development Kit Developer's Guide, Release 3.4 for NetBeans on Windows

E24265-06

Copyright © 2009, 2013, Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information on content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

Contents

Preface	xv
Audience	xv
Documentation Accessibility	xv
Conventions	xv
Related Documents	xvi
 1 Before You Begin	
Installing the Java SE Platform.....	1-1
Setting and Verifying Your Java SE PATH	1-1
Installing the Oracle Java ME SDK Platform	1-2
Installing and the Starting the NetBeans IDE	1-2
 2 Installing Plugins	
Downloading Oracle Java ME SDK Plugins	2-1
Installing Oracle Java ME SDK Plugins	2-1
Installing Plugins Using the Update Center	2-1
Installing NetBeans Plugins Manually	2-4
Verifying Your Installation.....	2-8
Quick Start.....	2-9
 3 Platforms	
Emulation Platforms	3-1
CLDC with MIDP	3-1
IMP-NG	3-2
CDC	3-3
Managing Java Platforms.....	3-3
Java ME Platforms	3-4
Create a Platform for Legacy CDC Projects	3-4
 4 Using Sample Projects	
Creating a Sample Project.....	4-1
Running a Project.....	4-2
Troubleshooting.....	4-4
Sample Project Overview	4-4

Configuring the Web Browser and Proxy Settings	4-7
Resolving Reference Problems	4-7
Running MIDP and CLDC Sample Projects	4-8
Running the AdvancedMultimediaSupplements Sample Project	4-9
Image Effects	4-9
Music Effects	4-9
Camera	4-9
Moving Helicopter	4-10
Running the Demos Sample Project	4-10
Colors	4-11
Properties	4-11
Http	4-11
FontTestlet	4-12
Stock	4-12
Tickets	4-13
ManyBalls	4-14
MiniColor	4-14
Chooser	4-14
HttpExample	4-14
HttpView	4-14
PushExample	4-14
Running FPDemo	4-15
Running Games	4-15
Running Network Demo	4-15
Socket Demo	4-15
Datagram Demo	4-16
Running PhotoAlbum	4-16
Running UIDemo	4-16
Running IMP-NG Sample Projects	4-17
Running the GPIODemo	4-17
Running the GPIODemo on the Emulator	4-18
Running the GPIODemo on the Reference Board	4-18
Running the I2CDemo	4-18
Running the NetworkDemoIMPNG	4-19
Running NetworkDemoIMPNG on the Emulator	4-19
Running NetworkDemoIMPNG on the Reference Board	4-19
Running the PDAPDemoIMPNG	4-20
Running the PDAPDemoIMPNG on the Emulator	4-20
Running PDAPDemoIMPNG on the Reference Board	4-21
Running the Pulse Counter (Data Collection) Demo	4-21
Configuring a Pulse Counter	4-22
Running the Light Tracker Demo	4-23
Running the System Controller Demo	4-23

5 Creating and Editing Projects

Project Types	5-1
MIDP Projects	5-1

CDC Projects	5-2
The Project Wizard	5-2
Create a MIDP Project	5-2
Create an IMP-NG Project	5-3
Create a CDC Project	5-3
Import a Legacy MIDP Project	5-4
Import a Legacy CDC Project	5-4
Working With Projects	5-5
View Project Files	5-6
Create a New MIDlet	5-6
Add Files to a Project	5-7
Search Project Files	5-7
Debugging MIDP and IMP-NG Projects	5-7

6 Viewing and Editing Project Properties

General Project Properties	6-1
Platform Selection	6-1
Editing Application Descriptor Properties	6-2
CDC Attributes	6-2
MIDP Attributes	6-2
Add an Attribute	6-2
Edit an Attribute	6-3
Remove an Attribute	6-3
MIDlets	6-3
Add a MIDlet	6-3
Edit a MIDlet	6-3
Remove a MIDlet	6-3
Change MIDlet Display Order	6-4
Push Registry	6-4
Add a Push Registry Entry	6-4
Enabling a Push Registry Entry	6-4
Remove a Push Registry Entry	6-4
Change Push Registry Display Order	6-4
API Permissions	6-4
Adding Permission Requests	6-4
Building a Project	6-5
Configuring Ant	6-5
Compiling	6-6
Adding Libraries and Resources	6-6
Creating JAR and JAD Files (Packaging)	6-7
Obfuscating	6-7
Signing	6-7
Signing CDC Projects	6-7
Exporting a Key	6-7
Running Settings	6-8
MIDP Project Run Options	6-8
CDC Project Run Options	6-9

7 Working With Devices

The Device Manager on Windows	7-1
Adding an External Device	7-3
Starting and Running Emulators	7-4
Starting an Emulator	7-4
The IMP-NG Emulator	7-5
The External Events Generator	7-7
IMP-NG Device Options	7-8
The Qualcomm IoE Emulator	7-8
The External Events Generator	7-9
The Serial Peripheral Interface (SPI) Tab	7-9
The Inter-Integrated Circuit (I2C) Tab	7-10
The CLDC Mobile Emulator	7-13
CLDC Application Management System	7-14
Mobile Emulator Menus	7-14
Running Projects Simultaneously on a Single Device	7-15
Emulator Menu Settings	7-16
The Application Menu	7-16
The Device Menu	7-17
Messages	7-17
Orientation	7-17
The Edit Menu	7-17
The Tools Menu	7-18
The View Menu	7-18
The Help Menu	7-19
Using the Device Selector	7-19
Viewing Device Properties	7-20
Platform Properties	7-20
Device Information	7-21
Device Properties	7-21
Setting Device Properties	7-21
General Device Properties	7-22
Monitor	7-22
IMP-NG Device Properties	7-22
Location Provider #1 and #2	7-24
SATSA	7-24
Bluetooth and OBEX	7-24
Running a Project from the Device Selector	7-24
Using the Custom Device Editor	7-24
Creating a Custom Device	7-25
Managing Custom Devices	7-25
Making Device Connections	7-26
Connecting to a UART Device	7-26

8 Finding Files in the Multiple User Environment

Switching Users	8-1
Installation Directories	8-1

NetBeans User Directories.....	8-2
Oracle Java ME SDK Directories.....	8-2
9 Profiling Applications	
Collecting and Saving Profiler Data in the IDE.....	9-1
Loading a .nps File	9-4
Importing a .prof File.....	9-4
10 Network Monitoring	
Monitor Network Traffic.....	10-1
Filter or Sort Messages	10-3
Save and Load Network Monitor Information.....	10-3
Clear the Message Tree.....	10-3
11 Monitoring Memory	
Enabling Tracing.....	11-1
Using the Memory Monitor.....	11-2
Viewing a Session Snapshot	11-4
12 Security and MIDlet Signing	
Security Domains	12-1
Setting Security Domains	12-2
Specify the Security Domain for an Emulator	12-2
Specify the Security Domain for a Project	12-2
Signing a Project.....	12-2
Sign a CLDC Project With a Key Pair	12-3
Sign a CDC Project	12-3
Managing Keystores and Key Pairs.....	12-3
Working With Keystores and Key Pairs	12-3
Create a Keystore	12-4
Add an Existing Keystore	12-4
Create a New Key Pair	12-4
Remove a Key Pair	12-5
Import an Existing Key Pair	12-5
Managing Root Certificates.....	12-5
13 Command Line Reference	
Run the Device Manager	13-1
Manage Device Addresses (device-address).....	13-1
Emulator Command Line Options.....	13-2
MIDlet Options	13-2
CDC Options	13-3
Debugging and Tracing Options	13-4
Command Line Profiling	13-4
Build a Project from the Command Line.....	13-5

Check Prerequisites	13-5
Compile Class Files	13-5
Preverify Class Files	13-6
Packaging a MIDlet Suite (JAR and JAD)	13-6
Command Line Security Features	13-7
Change the Default Protection Domain	13-7
Sign MIDlet Suites (jadtool)	13-7
Manage Certificates (MEKeyTool)	13-8
Generate Stubs (wscompile)	13-9
14 Logs	
Device Manager Logs	14-1
Device Instance Logs	14-1
15 API Support	
JCP APIs	15-1
Oracle APIs	15-2
16 JSR 75: PDA Optional Packages	
FileConnection API.....	16-1
PIM API.....	16-2
Running PDAPDemo	16-2
Browsing Files	16-2
The PIM API	16-2
17 JSR 82: Bluetooth and OBEX Support	
Setting OBEX and Bluetooth Properties	17-1
Running the Bluetooth Demo.....	17-2
Running the OBEX Demo.....	17-3
18 JSR 135: Mobile Media API Support	
Media Types	18-1
Media Capture	18-2
MMAPI MIDlet Behavior.....	18-2
Ring Tones	18-2
Download Ring Tones	18-2
Ring Tone Formats	18-2
Running AudioDemo	18-4
Running MMAPIDemos.....	18-4
Simple Tones	18-4
Simple Player	18-4
Video	18-6
Pausing Audio Test	18-6

19 JSR 172: Web Services Support

Generating Stub Files from WSDL Descriptors.....	19-1
Creating a New Mobile Web Service Client	19-2
Run JSR172Demo	19-4

20 JSR 177: Smart Card Security (SATSA)

Card Slots in the Emulator	20-1
Adjusting Access Control	20-2
Specifying PIN Properties	20-2
Specifying Application Permissions	20-2
Access Control File Example	20-4
Running the SATSA Demo	20-6

21 JSR 179: Location API Support

Setting the Emulator's Location at Runtime	21-1
Running the CityGuide Sample Project	21-3

22 JSR 205: Wireless Messaging

Using the WMA Console to Send and Receive Messages.....	22-1
Launching the WMA Console	22-1
WMA Console Interface	22-1
Emulator Phone Numbers	22-2
Sending a Text or Binary SMS Message	22-2
Sending Text or Binary CBS Messages	22-3
Sending MMS Messages	22-3
Receiving Messages in the WMA Console	22-4
Running WMADemo	22-4
WMADemo Push Registry Values	22-4
Running WMADemo OTA	22-4
Sending SMS Messages From WMA Console to an Emulator and Back	22-4
Sending CBS Messages from WMA Console to an Emulator	22-5
Sending MMS Messages from WMA Console to an Emulator	22-5
Running WMA Tool.....	22-6
smsreceive, cbsreceive, and mmsreceive	22-6
smssend	22-7
cbssend	22-7
mmssend	22-8

23 JSR 184: Mobile 3D Graphics

Choosing a Graphics Mode	23-1
Immediate Mode	23-1
Retained Mode	23-1
Quality Versus Speed	23-2
Content for Mobile 3D Graphics.....	23-2
Running Demo3D Samples.....	23-2

Life3D	23-2
RetainedMode	23-3
PogoRoo	23-3
24 JSR 211: Content Handler API (CHAPI)	
Using Content Handlers	24-1
Defining Content Handler Properties	24-2
Defining Content Handler Actions	24-3
Running the CHAPIDemo Content Browser	24-3
25 JSR 226: Scalable 2D Vector Graphics	
Running SVGDemo	25-1
SVG Browser	25-1
Render SVG Image	25-2
Play SVG Animation	25-2
Create SVG Image from Scratch	25-2
Bouncing Balls	25-2
Optimized Menu	25-3
Picture Decorator	25-3
Location Based Service	25-4
Running SVGContactList	25-5
26 JSR 239: Java Bindings for Open GL ES	
Open GL Overview	26-1
27 JSR 256: Mobile Sensor API Support	
Creating a Mobile Sensor Project	27-1
Using a Mobile Sensor Project	27-2
Creating a Sensor Script File	27-2
SensorBrowser	27-3
Marbles	27-4
28 JSR 257: Contactless Communication API	
Using ContactlessDemo	28-1
Tag File Formats	28-2
Script Format	28-3
A Installation and Runtime Security Guidelines	
Maintaining Optimum Network Security	A-1
B Tips for Legacy Toolkit Users	

List of Examples

14-1	Setting a Category Value	14-1
20-1	PIN Properties Example.....	20-2
20-2	Access Control File Record Format	20-2
20-3	Access Control File Example	20-4
21-1	Location Script Example	21-1
25-1	SVG File Example	25-2
27-1	Sensor Script File Format Example.....	27-2
28-1	Tag File Format Example	28-2
28-2	Tag Script File Format Example.....	28-3
28-3	Tag Script Sample	28-3

List of Figures

1-1	The NetBeans Start Screen.....	1-3
2-1	The NetBeans Plugins Manager.....	2-2
2-2	Adding a Plugin Portal	2-3
2-3	Creating a New Update Center	2-3
2-4	The Oracle Java ME SDK Plugins.....	2-4
2-5	The Plugins Manager Installed Tab.....	2-4
2-6	The NetBeans Plugins Manager Window	2-5
2-7	The Downloaded Tab and Add Plugins Button.....	2-5
2-8	Adding Plugins	2-6
2-9	Selecting Downloaded Plugins	2-6
2-10	The NetBeans IDE Installer	2-7
2-11	The Device Selector.....	2-8
2-12	The Java Platform Manager.....	2-9
4-1	The Project Property Screen	4-2
4-2	Running a Project from the Device Selector Menu	4-3
4-3	Cancelling the NetBeans Build Script	4-3
4-4	Project Warning Sign.....	4-7
4-5	Resolve Reference Problems Screen.....	4-8
4-6	The Home Button.....	4-17
4-7	Output Console Window Showing Pulse Counter Output.....	4-22
6-1	Emulator Command Line Switches.....	6-9
7-1	The Device Manager Icon	7-1
7-2	The Device Manager Menu	7-2
7-3	The Device Address Manager.....	7-2
7-4	The Registered Devices Screen	7-3
7-5	Adding a COM Port.....	7-4
7-6	The IMP-NG Emulator.....	7-5
7-7	The Qualcomm_IoE_Device Emulator	7-9
7-8	The External Events Generator SPI Tab.....	7-10
7-9	The External Events Generator I2C Tab with Available Sensors.....	7-11
7-10	Emulator Features.....	7-13
7-11	The Output Console Window	7-14
7-12	The Device Selector.....	7-20
7-13	Separate Device Properties Window.....	7-21
7-14	The Custom Device Editor.....	7-25
9-1	Profiling of AudioDemo	9-2
9-2	Attaching the Profiler	9-2
9-3	The Profiling Tab with Combined View Selected	9-3
9-4	Exporting Profile Data.....	9-3
9-5	Saving the Current View.....	9-3
10-1	Activating Network Activity.....	10-1
10-2	The Network Monitor Tab.....	10-2
10-3	The Network Monitor Toolbar.....	10-3
11-1	The Memory Monitor Tab	11-3
19-1	Creating a New Project and Adding a Mobile Application.....	19-2
19-2	Creating the Main Executable Class.....	19-2
19-3	The Java ME Web Service Client Information Dialog Box.....	19-3
21-1	External Events Generator Location Tab.....	21-2
21-2	The Location Settings Dialog Box.....	21-3
21-3	The Landmark Detail Screen.....	21-4
22-1	WMA Console and Output Windows	22-2
24-1	The Content Handlers Tab	24-1
24-2	The Content Handlers Properties Window	24-2
24-3	The Content Handlers Properties Window	24-3

25-1	Adding a Graphic	25-4
25-2	Highlighting a Graphic	25-4
25-3	A Location-Based Service Screen.....	25-5
27-1	Acceleration Sensor Screen.....	27-3

Preface

The Oracle® Java ME SDK is a mobile and embedded application development tool available as a plugin to the NetBeans IDE.

The Oracle Java ME SDK provides supporting tools and sample implementations for the latest in Java ME technology. It provides support for recent versions of the Connected Limited Device Configuration (CLDC), Information Module Profile - Next Generation (IMP-NG), and Connected Device Configuration (CDC) platforms.

Audience

This document is intended for Java ME application developers.

Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc>.

Access to Oracle Support

Oracle customers have access to electronic support through My Oracle Support. For information, visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info> or visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs> if you are hearing impaired.

Conventions

The following text conventions are used in this document:

Convention	Meaning
boldface	Boldface type indicates graphical user interface elements associated with an action, or terms defined in text or the glossary.
<i>italic</i>	Italic type indicates book titles, emphasis, or placeholder variables for which you supply particular values.
<code>monospace</code>	Monospace type indicates commands within a paragraph, URLs, code in examples, text that appears on the screen, or text that you enter.

Related Documents

For more information, see the following documents:

- See [Table 15–1](#) for supported API documentation links.
- To see documentation for the Oracle Java Wireless Client and CLDC Hotspot go to <http://docs.oracle.com/javame/mobile.html> and look under Documentation for Device Makers
- For legacy SDK documentation, see:
<http://docs.oracle.com/javame/developer.html>

Legacy Sun Java Wireless Toolkit documentation is also available from this site.

Before You Begin

The Oracle® Java Micro Edition (Java ME) Software Development Kit (SDK) is a natural starting point for learning and using Java ME technology. The focus of the SDK is to provide emulation and deployment assistance during the development process. This chapter introduces the SDK and provides a quick introduction to using the SDK.

Using this simple yet powerful tool you can create, edit, compile, package, and sign an application. After testing your application in the Oracle Java ME SDK emulation environment, you can move to deploying and debugging on an external device.

This chapter provides information you need to ensure that your Microsoft Windows XP (32-bit) or Windows 7 (32-bit or 64-bit) platform is correctly set up for working with Oracle Java ME SDK. Both Windows XP and Windows 7 must include the most recent Microsoft service packs.

Installing the Java SE Platform

To properly run the Oracle Java ME SDK software and its associated Tools, you must have Java Platform, Standard Edition (Java SE), Version 7, Update 11 (or later) installed on your computer.

This guide assumes you have already installed the Java SE platform. If you have not installed Java SE, you can download it from the following location:

<http://www.oracle.com/technetwork/java/javase/downloads>

The Java SE platform must also be in your PATH.

Setting and Verifying Your Java SE PATH

To verify if Java SE platform is set in your PATH:

1. In the Windows command line, type:
`C:\>echo %PATH%`
2. If Java SE is properly installed, you see a path to the default installation directory:
`C:\>Program Files\Java\jdk1.7.0_x`
3. If not, you need to add Java SE to your PATH.

Note: Setting the PATH may require using a Windows short name. To see top-level Windows short names, type `C:\>dir /x`

4. Set the Java SE variable, JDK_DIR:

```
C:\>set JDK_DIR=C:\Program Files\Java\jdk1.7.0_13
```

5. Add JDK_DIR to your PATH:

```
C:\>set PATH=%PATH%;%JDK_DIR%\bin
```

6. To verify the version of your Java SE platform, type:

```
C:\>java -version
```

The version number shown in the output should be version 1.7.0_11 or higher.

Installing the Oracle Java ME SDK Platform

Follow these steps to install the Oracle Java ME SDK 3.4.

1. If you have previously installed an earlier version of Oracle Java ME SDK, uninstall the previous version as shown below.

Note: If you are installing Oracle Java ME SDK for the first time, skip to Step 2.

- If you have Oracle Java ME SDK data to save, please copy it to a safe location before continuing.
 - In the Windows system tray, right click on the emulator icon and select Exit.
 - From the Windows Programs menu, select the previous version and select Uninstall from the submenu. The Installer opens.
 - On the first page check the option to remove the user data directory.
 - Follow the prompts.
2. Download the SDK from:
<http://www.oracle.com/technetwork/java/javame>
 3. Select download in the right column.
 4. Download the Oracle Java ME SDK executable.
 5. Double-click on the ME SDK executable. When the installer starts, follow the prompts.


Installing and the Starting the NetBeans IDE

If you do not already have the NetBeans 7.3 IDE installed on your system, you can download it here:

<http://dlc.sun.com.edgesuite.net/netbeans/7.3/final/>

Next, optionally select your Language and Platform, and then download the version that contains all supported technologies. The approximate size of executable distributive is 198 MB. Once you have downloaded the NetBeans installation module, do the following:

1. Unzip the NetBeans distribution zip file into the C:\Program Files directory.
2. In the C:\Program Files\NetBeans 7.3\bin directory, click on netbeans.exe to launch NetBeans, as shown in [Figure 1-1](#).

Figure 1–1 The NetBeans Start Screen

The Oracle Java ME SDK is also a plugin to the Eclipse IDE. For more information on using Oracle Java ME SDK with the Eclipse IDE, see *Oracle Java Micro Edition Software Development Kit Developer's Guide for Eclipse*.

Installing Plugins

This chapter describes the NetBeans integrated development environment. NetBeans provides a rich, visual environment for developing embedded applications and numerous tools to improve the programming process.

Oracle Java ME SDK provides two plugins for working with NetBeans:

- Java ME SDK Tools plugin
- Java ME SDK Demos plugin

The Java ME SDK Demos plugin is optional, but recommended.

Downloading Oracle Java ME SDK Plugins

To download the Oracle Java ME SDK Plugins file for NetBeans (oracle-jmesdk-3-3-rr-nb-plugins.zip) go to the following location:

<http://www.oracle.com/technetwork/java/javame/javamobile/download/sdk>

Installing Oracle Java ME SDK Plugins

There are two ways to install the Oracle Java ME SDK Plugins:

- ["Installing Plugins Using the Update Center"](#)
- ["Installing NetBeans Plugins Manually"](#)


Note: Using the NetBeans Update Center to install the plugins is recommended. However, installing the plugins manually also works.

To get the plugins ready for installation, start NetBeans as described in ["Installing and the Starting the NetBeans IDE."](#)


Installing Plugins Using the Update Center

To install the NetBeans Plugins using the NetBeans Update Center:


1. Select Tools > Plugins to open the NetBeans Plugins manager, as shown in [Figure 2-1](#).

Figure 2–1 The NetBeans Plugins Manager


2. Click the Settings tab. This displays the available update centers, as shown in [Figure 2–2](#).

Figure 2–2 Adding a Plugin Portal


3. Click the Add button. In the new window, type a provider name and a URL for the location that contains the plugin center files, as shown in [Figure 2–3](#).

Figure 2–3 Creating a New Update Center

4. When plugins are detected, they are displayed on the Available Plugins tab. If you do not see them, click the Check for Updates button.
 - Locate the Oracle Java ME SDK plugins.
 - In the Install column check the desired plugins, then click the Install button.

Figure 2–4 The Oracle Java ME SDK Plugins

5. Restart NetBeans.
6. In the Plugins Manager Settings tab, enable all available update centers.
7. In the Installed tab, check Show details (above the plugin list) and sort by category to easily find the Java ME SDK Tools plugins.
 - Make sure the plugins you installed are active (with a green check mark), as shown in [Figure 2–5](#).
 - If the Oracle Java ME SDK plugins are not Active, check the Select boxes for the plugins and click Activate.

Figure 2–5 The Plugins Manager Installed Tab


The Oracle Java ME SDK is ready to use. For more information on how to verify your plugin installation, see ["Verifying Your Installation."](#)

Installing NetBeans Plugins Manually


To install the NetBeans Plugins manually.

1. Extract the contents of the NetBeans Plugins file to a directory on your local machine. Make note of the location.
2. Open the NetBeans Plugins Manager. Select:
Tools > Plugins
3. Uninstall previous plugins.
 - Go to the Installed tab and click Show details, as shown in [Figure 2–6](#).
 - Check Java ME SDK Tools and Java ME SDK Demos.


Note: If the previous plugins have already been uninstalled, go to Step 6.

Figure 2-6 The NetBeans Plugins Manager Window


- Click Uninstall.
 - Restart when requested.
4. Re-open the Plugins Manager and click the Downloaded tab, as shown in [Figure 2-7](#).
 5. Click the Add Plugins button.

Figure 2-7 The Downloaded Tab and Add Plugins Button

6. In the file browser, go to the directory in which you have extracted the contents of the NetBeans Plugins.
7. Select all the .nbm files and click Open, as shown in [Figure 2-8](#).


Figure 2–8 Adding Plugins

8. Go to the Downloaded tab and select all downloaded plugins, as shown in [Figure 2–9](#), and click Install.

Figure 2–9 Selecting Downloaded Plugins

9. When the NetBeans IDE Installer screen is displayed, as shown in [Figure 2-10](#), click Next.
 - Accept the license terms and click Install.
 - If additional Validation screens appear, click Continue.

Figure 2-10 The NetBeans IDE Installer



10. Click Finish to restart NetBeans.
11. Select Tools > Plugins to display the Plugins screen.
12. In the Installed tab, check Show details and click Category to sort the plugins.
 - Find the Java ME SDK Tools and Java ME SDK Demos plugins in the list.
 - Make sure the plugins you installed are Active (you should see a green check mark), as shown in [Figure 2-6](#).
 - If the Oracle Java ME SDK plugins are not Active, check the Select boxes for the plugins and click Activate.
13. When your Oracle Java ME SDK plugins are Active, click Close.


The Oracle Java ME SDK is ready to use. For more information on how to verify your plugin installation, see ["Verifying Your Installation."](#)

Verifying Your Installation

Once you have installed the Oracle Java ME SDK Plugins into NetBeans (using the Update Center or by manual installation), the Oracle Java ME SDK platform is installed into the NetBeans IDE. To verify a successful installation, do the following:


1. To verify the Active Device Manager, select Tools > Java ME > Active Device Manager, and select the latest version (Oracle Java ME SDK 3.4).
2. To view available Oracle Java ME SDK 3.4 devices, select Tools > Java ME > Device Selector. The ME SDK devices are listed, as shown in [Figure 2–11](#).

Figure 2–11 The Device Selector



3. To display the new Oracle Java ME SDK platform, select Tools > Java Platforms. This displays the Java Platform Manager with the new platform, as shown in [Figure 2–12](#).

Figure 2–12 The Java Platform Manager



The Oracle ME SDK Platform is now ready for you to work with, to create a new project and develop code.

Quick Start

The following tips offer some hints for getting started as quickly as possible.

- Access the documentation. The online help is the primary documentation for the SDK. Many windows and dialogs feature a help button that opens context-sensitive help in the help viewer. You can also type F1.

Select **Help > Help Contents** to open the JavaHelp Online Help viewer. Remember to use the search capability and the index to help you find topics.

Note: If you require a larger font size, the help topics are also available as a printable PDF and a set of HTML files.

- Run sample projects. Running sample projects is a good way to become familiar with the SDK. See ["Running a Project"](#) for a general overview of how to run a project.
- See the Projects window and the Files window for a visual overview of the logical and physical layout of a project. When viewing items in the tree, use the context menu (right-click) to see the available actions. See ["Working With Projects."](#)
- A project has a default device that is used when you run it from the Toolbar (the green arrow), **Run > Run Project**, or **Run** on the project's context menu. To see a project's default device, right-click the project and select **Properties**. Select the

Platform category to see the default device displayed in the Device field. To reset the Device make another choice from the drop down menu.

- To run an application on different devices without changing the default device, right-click on the project and select **Run With** from the context menu. Select a different device and click **OK**.
- The emulator is an independent process, and when it has started it is a separate process from the build process running in NetBeans. Stopping the build process or closing a project does not always affect the application running in the emulator. You must be sure to terminate the application (the emulator can remain open). See ["Running a Project."](#)
- The SDK provides two unique emulator instances for most devices. For example, IMPNGDevice1 and IMPNGDevice2 are the same except for the device number and the phone number, so you can perform tests that require two devices (messaging, for example) without customization. If you want to create your own device, see ["Using the Custom Device Editor."](#)

This chapter describes the Oracle Java ME SDK technology platforms, also called stacks. They are: "CLDC with MIDP," "IMP-NG," and "CDC," as discussed in "Emulation Platforms."

A project runs on a particular emulation platform. The Device Manager determines whether a device is appropriate for your project based on the platform, the APIs your application uses, and a set of device properties. If you run an application and an appropriate emulator or device is currently running, the SDK automatically installs and runs your application in the current device so that you do not have to launch the emulator repeatedly.

Emulation Platforms

An emulator simulates the execution of an application on one or more target devices. An emulation platform enables you to understand the user experience for an application and test basic portability. For example, a platform enables you to run applications on several sample devices with different features, such as screen size, keyboard, runtime profile and other characteristics.

Oracle Java ME SDK provides the following emulation platforms:

- Connected Limited Device Configuration (CLDC) with Mobile Information Device Profile (MIDP)
- CLDC with MIDP, Information Module Profile - Next Generation (IMP-NG) subset
- Connected Device Configuration (CDC) with Advanced Graphics and User Interface (AGUI)
- CDC with Personal Basis Profile (PBP)

All platforms include predefined devices with different screen sizes, runtime profiles, and input methods.

See "CLDC with MIDP," "IMP-NG," and "CDC."

CLDC with MIDP

CLDC/MIDP applications conform to the following specifications:

- Connected Limited Device Configuration 1.1
<http://jcp.org/en/jsr/detail?id=139>
- Mobile Information Device Profile 2.1
<http://download.oracle.com/otndocs/jcp/midp-2.1-mrel-oth-JSpec>

- All the JSRs listed in ["JCP APIs"](#)

CLDC/MIDP applications are targeted for devices that typically have the following capabilities:

- A 16-bit or 32-bit processor with a clock speed of 16MHz or higher
- At least 160 KB of non-volatile memory allocated for the CLDC libraries and virtual machine
- At least 192 KB of total memory available for the Java platform
- Low power consumption, often operating on battery power
- Connectivity to some kind of network, often with a wireless, intermittent connection and limited bandwidth

Typical devices might be cellular phones, pagers, low-end personal organizers, and machine-to-machine equipment. In addition, CLDC can also be deployed in home appliances, TV set-top boxes, and point-of-sale terminals.

The SDK provides two default emulators to support CLDC:

- `ClamshellJavaMEPhone1`
A flip phone with a primary display and a secondary display.
- `JavaMEPhone1` and `JavaMEPhone2`
A flat touch screen device.

These devices support CLDC 1.1, MIDP 2.1, and optional packages for JSRs 75, 82, 135, 172, 177, 179, 184, 205, 211, 226, 234, 239, 256, 257, and 280.

See [Chapter 4, "Using Sample Projects"](#) [Chapter 5, "Creating and Editing Projects,"](#) and [Chapter 7, "Working With Devices."](#)

IMP-NG

JSR 228 describes the *Information Module Profile - Next Generation*, referred to as IMP-NG. This JSR extends and enhances *JSR 195: Information Module Profile*.

The IMP-NG implementation depends upon CLDC 1.1. It is a strict subset of MIDP 2.1 that excludes MIDP 2.1 graphical display capabilities, resulting in a smaller footprint appropriate for Information Modules (IMs). Potential devices for CLDC with IMP-NG might be modems, home electronics devices, or industrial metering devices.

An IMP-NG application is an IMlet, and multiple IMlets in a single JAR file form an IMlet suite. When creating an IMlet project you follow the same process as that you use to create a Java ME Mobile Application project and select an IMP-NG device. The device selection determines the supported JSRs.

The IMP-NG stack supports the following JCP APIs: JSRs 75, 120, 172, 177, 179, 257, and 280. In addition, Oracle provides APIs to support IMP-NG development, as described in ["Oracle APIs."](#)

The Oracle Java ME SDK implementation provides IMP-NG emulation, on-device tooling connectivity to external devices, and Attention (AT) Command support. The SDK emulator supports IMP-NG with `IMPNGDevice1` and `IMPNGDevice2` skins and provides simple interfaces for Inter-Integrated Circuit (I²C), Serial Peripheral Interface (SPI), General Purpose Input/Output (GPIO), and Memory-mapped I/O (MMIO) buses. The emulator's external event generator provides a way for you to inject calls to emulate AT Commands, alter basic pin and port information for GPIO, and memory block values.

See ["Running IMP-NG Sample Projects."](#)

CDC

A CDC (<http://jcp.org/en/jsr/detail?id=218>) application is an application targeted for network-connected consumer and embedded devices, including high-end mobile phones, smart communicators, high-end PDAs, and set-top boxes.

Devices that support CDC typically include a 32-bit microprocessor or controller and make about 2 MB of RAM and 2.5 MB of ROM available to the Java application environment.

CDC is based upon the open source project phoneME Advanced, found at <http://java.net/projects/phoneme>. A CDC application conforms to the Connected Device Configuration with a set of profiles that include Personal Basis Profile, Foundation Profile, and AGUI:

- CDC 1.1 with PBP 1.1 (<http://jcp.org/en/jsr/detail?id=217>)
- Foundation Profile 1.1
(<http://jcp.org/aboutJava/communityprocess/final/jsr219/index.html>)
- AGUI 1.0 (<http://www.jcp.org/en/jsr/detail?id=209>)

The SDK provides three default emulators to support CDC:

- Default CdcPbpPhone1
CDC 1.1, PBP 1.1, Foundation Profile (FP) 1.1
- VgaAGUIPhone1
CDC 1.1, PBP 1.1, FP 1.1 and AGUI 1.0
- VgaCdcPhone1
CDC 1.1, PBP 1.1, FP 1.1

See ["Project Types"](#) and ["Viewing Device Properties"](#) for more information on project types and device properties.

Managing Java Platforms

To view the Java Platform Manager, click the **Tools** menu and select **Java Platforms**. Alternatively, right-click a project, select **Properties** from the context menu, select the Platform category, and select the Manage Emulators button to open the Java Platform Manager.

The Java Platform Manager is a tool for managing different versions of the Java Development Kit (JDK) and customizing Java platforms that your applications depend on. You can add source files and Javadoc documents to the existing platforms.

The Oracle Java ME SDK pre-registers CDC, J2ME, and Java SE (the JDK serves as the default platform) for version 3.4. These platforms have similar options:

- **Devices.** (J2ME) View all the CLDC and IMP-NG devices that the Device Manager has discovered. Click Refresh to reconfigure the platform and refresh the list.
- **Classes.** (CDC) View the platform's classpaths. A class's location in the list determines its place in the classpath. For the CDC platform, you can add a JAR or folder containing additional classes. You can also use the Move Up and Move Down buttons to change the class position.

- **Sources.** (CDC, J2ME, and Java SE) Add JAR files or source files to the Sources tab to register source code.
- **Javadoc.** (CDC, J2ME, and Java SE) Add Javadoc documentation to support any new classes or source files you have added.
- **Tools and Extensions.** (For J2ME, only as Devices) See ["Java ME Platforms"](#) for more information.

Java ME Platforms

In the Oracle Java ME SDK the platforms are embedded Java runtimes specifically for resource-constrained devices. Because the NetBeans Mobility pack is installed for Java ME, you see the legacy 3.2 platforms coexisting with version 3.4 platforms and devices. Each platform has its own set of devices and optional packages.

Note: If you cannot see the 3.4 devices in the Device Selector, select **Tools > Java ME > Active Device Manager** and select **Java(TM) ME Platform SDK 3.4**.

Applications that worked in previous platform versions might not run on the current version, and vice versa. Follow these steps to set a project's platform options.

1. Right-click on a project and select Properties from the context menu.
2. Select the Platform category. Be sure that the Emulator Platform is set to version 3.4.
3. The device configuration should be automatically selected, but the Device Profile might not be explicitly selected. Be sure to select a profile.
4. Optional. Check any optional packages that are required to support the current project. (If this is an IMP-NG project you also see the Oracle APIs listed as optional packages. See ["Oracle APIs"](#)).

Click OK.

5. Rebuild the project and run.

Create a Platform for Legacy CDC Projects

The Oracle Java ME SDK version 3.4 platform name for CDC does not match the name in the legacy CDC toolkit and the CDC Mobility Pack. The legacy name is "Sun Java Toolkit 1.0 for Connected Device Configuration" while the SDK name is "CDC Oracle Java(TM) Platform Micro Edition SDK 3.4." To ensure a successful import, you can create a new platform and give it the legacy name.

The following procedure enables you to import legacy CDC projects without Reference errors (see ["Resolving Reference Problems"](#)).

1. Click the **Tools** menu and select **Java Platforms**. Select "CDC Oracle Java(TM) Platform Micro Edition SDK 3.4." and in the Classes tab, note the libraries required for the platform.
2. Click **Add Platform...**
3. Select Java ME CDC Platform Emulator and click **Next**.
4. On the Choose Platform page, select the SDK installation directory. Click **Next**.

5. On the Platform Name page, type "Sun Java Toolkit 1.0 for Connected Device Configuration" in the Name field. In the Sources tab, click **Add** and select the following libraries from the SDK installation directory: `agui_1.0.jar`, `cdc_1.1.jar`, `fp_1.1.jar`, `pbp_1.1.jar`, and `secop_1.0.jar`.

Click **Finish** and **Close**.

See ["Import a Legacy CDC Project"](#) and ["Resolving Reference Problems."](#)

Using Sample Projects

The Oracle Java ME SDK sample projects introduce you to the emulator's API features and the SDK features, tools, and utilities that support the various APIs. These features can help you customize the sample projects or create applications of your own.

Note: Before using the Oracle Java ME SDK demo applications, see "Installation and Runtime Security Guidelines" in [Appendix A](#). Some demos use network access and open ports, and do not include protections against malicious intrusion. If you choose to run the sample projects, you should ensure your environment is secure.

For instructions on running projects, see the following topics:

- ["Creating a Sample Project"](#)
- ["Running a Project"](#)
- ["Troubleshooting"](#)
- ["Sample Project Overview"](#)
- ["Configuring the Web Browser and Proxy Settings"](#)
- ["Resolving Reference Problems"](#)
- ["Running MIDP and CLDC Sample Projects"](#)
- ["Running IMP-NG Sample Projects"](#)

Creating a Sample Project

Sample applications are installed in a separate NetBeans plugin. Do not run or edit these projects directly. You create a new project that is an instance of the sample project.

The default location for Oracle Java ME SDK projects is the default NetBeans project directory. Each project has a `src` directory that contains Java programming language source code. For example, the default location of the source code for the SMS sender MIDlet (`example.sms.SMSSend`) in `WMADemo` resides in the following location:

```
username\My Documents\NetBeansProjects\WMADemo\src\example\sms\SMSSend.java
```

1. Click the **File** menu and select **New Project**. In the Categories window, click **Samples** and select **Java ME SDK 3.4**. Single-click a sample project name and click **Next**.


2. Accept Name and Location page default values or provide your own. Click **Next**.
3. Select an emulator platform and a device. Depending on the project you select to run, you might need to select a different profile (for example, you might need to run the MIDP 2.1 device profile rather than MIDP 2.0). Note, changing the device affects the possible device profiles. Click **Finish**.

The project is added to the Project window.

Note: If you cannot see the Project window, click the **Window** menu and select **Projects**. To see console output, select **Window > Output > Output**.

4. Set the project's default execution mode. Right-click on a project and select **Properties** from the context menu, then select the Running category.

Figure 4–1 The Project Property Screen



If you want to install the application in the emulator each time it is run, select Execute through OTA (Over the Air Provisioning).

If the application does not need to be installed in the emulator, click Regular Execution (see ["Security Domains"](#)).


Running a Project

Create your own project, or instantiate one of the sample projects provided with the SDK as described in ["Creating a Sample Project."](#)

1. Use one of the following methods to run a project:
 - Right-click the project and select **Run** from the context menu.

- To run the main project (which is shown in bold text in the Projects window), click the green **Run** button in the Toolbar or press F6. To set the main project, click the **Run** menu and select **Set Main Project**. Select a project from the dropdown menu.
- To run an open project on a different device or to change the execution mode, select the device in the Device Selector window (select **Tools > Java ME > Device Selector**). Right-click on a device and select **Run Project** or **Run Project via OTA** from the context menu. Pull right to see a listing of open projects. Only open projects that can run on the selected device are listed. (Not all open projects are shown in the list.)

Figure 4–2 Running a Project from the Device Selector Menu



- To run a project on an emulator, click the Windows **Start** button, open All Programs. Click **Java(TM) ME Platform SDK 3.4** and select **Java ME SDK CLDC Emulator** or **Java ME SDK IMP-NG Emulator**, then drag and drop the project's JAD or JAR file onto the emulator. Click **OK** in the Run MIDlet (or IMlet) Suite dialog box.

The device emulator window opens with the demo application running. If the demo is a MIDlet suite you might have to select a MIDlet to launch.

2. As the sample project runs, soft keys might be enabled below the screen on the left or right side.

You use soft keys to install or launch an application, open a menu, exit, or perform some other action. Some demos include these instructions in the application.

See [Table 4–1](#) or [Table 4–3](#) for instructions on running samples.

3. When you are finished viewing the application, go to the emulator's Application menu and select Exit to close the emulator and stop the execution of the project's build script.

When the emulator is launched, it runs as an independent process. Pressing the red stop button in the NetBeans Output window terminates the build script, but it does not close the emulator instance. You can also terminate the build script by clicking the X next to the progress meter at the bottom of the IDE.

Figure 4–3 Cancelling the NetBeans Build Script



Likewise, closing the NetBeans IDE does not affect the emulator instance. In the emulator, click the **Application** menu and select **Exit** or press the emulator's exit button (the X) on the upper right to ensure that both the emulator process and the project build process close.

Periodically, you might want to clear a device's database especially after you have run several projects. Right-click the device and select Clean RMS storage files. When you run the command, a completion notice is displayed in the IDE's status bar.

Troubleshooting

Sometimes even a "known good" application, such as a sample project, does not run successfully. The problem is usually your environment.

- Some demonstrations require specific setup and instructions. For example, if a sample uses web services and you are behind a firewall, you must configure the emulator's proxy server settings or web access fails. See ["Configuring the Web Browser and Proxy Settings."](#)
- If an application must run over the air (OTA), the SDK automatically installs it in the device instance. See ["Emulator Command Line Options."](#)

MIDlet Suites use `runMIDlet` to perform the installation:

```
installdir\runtimes\cldc-hi\bin\runMidlet.exe
```

IMlet Suites also use `runMIDlet` to perform the installation, but from the `impng` directory:

```
installdir\runtimes\impng\bin\runMidlet.exe
```

CDC platforms install applications as follows:

```
installdir\runtimes\cdc-hi\bin\cvm.exe
```

Because these programs are launched remotely, virus checking software can prevent them from running. If this happens, the project compiles, but the emulator never opens. In the console you see warnings that the emulator cannot connect.

Consider configuring your antivirus software to exclude `runMidlet` and `cvm` from checking.

Sample Project Overview

The Oracle Java ME SDK includes demonstration applications that highlight some technologies and APIs that are supported by the emulator.

Most demonstration applications are simple to run. ["Running a Project"](#) contains instructions for running most demonstrations. Sample projects usually have some additional operation instructions.

[Table 4–1](#) lists the MIDP/CLDC demonstration applications available in this release.

[Table 4–2](#) lists the MIDP/IMP-NG demonstration applications available in this release.

[Table 4–3](#) lists the CDC sample projects available in this release.

Table 4–1 MIDP/CLDC Sample Projects

Sample	Optional Package	Description	Instructions
Advanced Multimedia Supplements	JSR 234	Demonstrates 3D audio, reverberation, image processing, and camera control.	"Running the AdvancedMultimediaSupplements Sample Project"
AudioDemo	MMAPI 1.1	Demonstrates audio capabilities, including mixing and playing audio with an animation.	Chapter 18, "JSR 135: Mobile Media API Support"
BluetoothDemo	JSR 82	Demonstrates device discovery and data exchange using Bluetooth.	Chapter 17, "JSR 82: Bluetooth and OBEX Support"
CHAPIDemo	JSR 211	A content viewer that also uses MediaHandler.	Chapter 24, "JSR 211: Content Handler API (CHAPI)"
CityGuide	JSR 179	A city map that displays landmarks based on the current location.	Chapter 21, "JSR 179: Location API Support"
ContactlessDemo	JSR 257	Emulates detection of RFID tags.	Chapter 28, "JSR 257: Contactless Communication API"
Demos	MIDP 2.1	Includes various examples: animation, color, networking, finance, and others.	"Running the Demos Sample Project"
FPDemo	CLDC 1.1	Simple floating point calculator.	"Running FPDemo"
Games	MIDP 2.1	Includes TilePuzzle, WormGame, and PushPuzzle.	"Running Games"
JSR172Demo	JSR 172	Demonstrates how to use the JSR 172 API to connect to a web service from a MIDlet.	Chapter 19, "JSR 172: Web Services Support"
MMAPIDemos	MMAPI	Demonstrates MMAPI features, including tone sequences, MIDI playback, sampled audio playback, and video.	Chapter 18, "JSR 135: Mobile Media API Support"
Multimedia	MMAPI	Demonstrates different video playback formats.	Chapter 18, "JSR 135: Mobile Media API Support"
NetworkDemo	MIDP 2.1	Demonstrates how to use datagrams and serial connections.	"Socket Demo" and "Datagram Demo"
ObexDemo	JSR 82	Demonstrates device discovery and data exchange using Bluetooth.	Chapter 17, "JSR 82: Bluetooth and OBEX Support"
PDAPDemo	JSR 75	Demonstrates how to manipulate contacts, calendar items, and to-do items. Demonstrates accessing local files.	Chapter 16, "JSR 75: PDA Optional Packages"
PhotoAlbum	MIDP 2.1	Demonstrates a variety of image formats.	"Running PhotoAlbum"

Table 4–1 (Cont.) MIDP/CLDC Sample Projects

Sample	Optional Package	Description	Instructions
SATSADemo	JSR 177	Demonstrates communication with a smart card and other features of SATSA.	Chapter 20, "JSR 177: Smart Card Security (SATSA)"
SATSAJCRMIDemo	JSR 177	Shows how to use the SATSA-Java Card Remote Invocation method.	Chapter 20, "JSR 177: Smart Card Security (SATSA)"
Sensors	JSR 256	The SensorBrowser and Marbles game demonstrate sensor input.	Chapter 27, "JSR 256: Mobile Sensor API Support"
SVGContactList	JSR 226	Uses SVG to create a contact list displayed with different skins.	Chapter 25, "JSR 226: Scalable 2D Vector Graphics"
SVGDemo	JSR 226	Uses different SVG rendering techniques.	Chapter 25, "JSR 226: Scalable 2D Vector Graphics"
UIDemo	MIDP 2.1	Showcases the breadth of MIDP 2.1's user interface capabilities.	"Running UIDemo"
WMADemo	WMA 2.0	Shows how to send and receive SMS, CBS, and MMS messages.	Chapter 22, "JSR 205: Wireless Messaging"
XMLAPIDemo	JSR 280	Uses DOM and STAX APIs to create an XML sample and SAX, DOM and StAX APIs to parse the sample.	Follow the instructions the application provides.

Table 4–2 IMP-NG Sample Projects

Sample	Description	Instructions
GPIODemo	Changes the state of LEDs in an emulator or reference platform.	"Running the GPIODemo"
I2CDemo	Writes data to a slave and then retrieves it.	"Running the I2CDemo"
NetworkDemoIMPNG	Allows connection and communication between a server and a client instance.	"Running the NetworkDemoIMPNG"
PDAPDemoIMPNG	Demonstrates management of a file system in the emulator.	"Running the PDAPDemoIMPNG"
Pulse Counter (Data Collection) Demo	Sends pulses to a counter and tracks them when they arrive using a timestamp.	"Running the Pulse Counter (Data Collection) Demo"
LightTrackerDemo	Controls LEDs on a reference platform.	"Running the Light Tracker Demo"
SystemControllerDemo	Demonstrates IMlet lifecycle on a reference platform.	"Running the System Controller Demo"

Table 4–3 CDC Sample Projects

Sample	Optional Package	Description	Instructions
AGUIJava2DDemo	JSR 209	This standalone application is a Java SE application adapted for the CDC environment. It demonstrates the graphical and animation capabilities of the Java 2D™ API.	Click the blue arrows to page through the various images and animations. The applications focus on curves. Click the AA icon to see how antialiasing affects appearance.
AGUISwingSet2	JSR 209	Functional tools such as buttons, sliders, and menus implemented with Swing.	Click through the tabs to view the controls and animations.

Configuring the Web Browser and Proxy Settings

If you are behind a firewall you must configure the proxy server so that MIDP applications using web services can succeed.

Note: CDC emulators do not work through a proxy. Communications such as downloading images from the Internet fail on CDC emulators.

The settings are typically the same as those you are using in your web browser.

1. Select **Tools > Options > General**.

2. Select a Proxy Setting:

- No Proxy
- Use System Proxy Settings
- Manual Proxy Settings

To set the HTTP Proxy, fill in the proxy server address field and the port number. The HTTP Proxy Host is the host name or numeric IP address of the proxy server used to connect to HTTP and FTP sites. The Proxy Port is the port number of the proxy server.

To set the HTTPS or Socks proxy, click More and fill out the Advanced Proxy Options form.

Resolving Reference Problems

Sometimes when you open a project you can see it has a reference warning. In the Projects tab the project name is red, and the icon shows a warning symbol, as seen below:


Figure 4–4 Project Warning Sign

Usually this warning means the project refers to a platform, file, or library that cannot be found.

If you are using an old project it might be referring to a platform or device that is not installed. In this case, edit the project properties and select an available platform and device as described in ["Java ME Platforms,"](#) then rebuild the project.

If the problem is not the platform, right-click the project and select **Resolve Reference Problems**.

Figure 4–5 *Resolve Reference Problems Screen*



The window displays the missing file, the problem, and a possible solution. In this case the project probably used a literal path to the file `keystore.ks`. Clicking the **Resolve...** button opens a file browser so you can find the missing keystore file. The default location is as follows:

`installdir\runtimes\cldc-hi\lib` (for CLDC)

`installdir\runtimes\impng\lib` (for IMP-NG)

`installdir\runtimes\cdc-hi\lib` (for CDC)

Locate and select the file. You receive confirmation that the problem is resolved, and you can now click **Close**.

Running MIDP and CLDC Sample Projects

This topic gathers MIDP and CLDC samples that are not discussed in separate chapters. This is the case when a sample uses many JSRs, or when a supported JSR does not have any special implementation details.

- ["Running the AdvancedMultimediaSupplements Sample Project"](#)
- ["Running the Demos Sample Project"](#)
- ["Running FPDemo"](#)
- ["Running Games"](#)
- ["Running Network Demo"](#)
- ["Running PhotoAlbum"](#)

- ["Running UIDemo"](#)

For other CLDC demos, see [Table 4-1](#).

Running the AdvancedMultimediaSupplements Sample Project

This MIDlet suite demonstrates the power of JSR 234 Advanced Multimedia Supplements (AMMS). It consists of the following MIDlets:

- ["Image Effects"](#)
- ["Music Effects"](#)
- ["Camera"](#)
- ["Moving Helicopter"](#)

Image Effects

This MIDlet demonstrates standard image processing operations.

- Launch the Image Effects MIDlet.
- Select input and output image formats, and press Done. The input image and output images are displayed simultaneously.
- Select an effect from the Menu and click the Done button to apply a transformation, effect or overlay. The source image is shown above and the processed image is shown below. Some items, Set Transforms, for example, can perform several operations in a single transaction.

The menu options are as follows:

- Reset - Set transforms, effects, and overlays to the initial state.
- Monochrome Effects - Activate grayscale rendering.
- Negative Effect - Reverse dark and light areas.
- Set Formats - Select an input object type and an output image format.
- Set Effect Order - Specify the order in which transforms, effects and overlays are applied.
- Set Transforms - Change width and height scale, border, and rotation options.
- Set Overlays - Specify the color and orientation of a color block overlay.

Music Effects

Demonstrates the advanced audio capabilities of the Advanced Multimedia Supplements. As an audio file loops continuously, you can adjust the volume, and reverberation settings.

Camera

This MIDlet demonstrates how the Advanced Multimedia Supplements provide control of a device's camera. The screen shows the viewfinder of the camera (simulated with a movie). You can use commands in the menu to change the camera settings and take and manage snapshots.

- Zoom settings - digital and optical zoom settings 100-300 in increments of 20. Make a selection and press Back.

- View gallery - View a list of the snapshots stored in:
username\javame-sdk\3.4\work\devicename\appdb\filesystem\root1. Select Display to see the snapshot. You have the option to delete the file from disk.
- Set flash mode - Off, AUTO, AUTO_WITH_REDEYEREDUCE, FORCE, FORCE_WITH_REDEYEREDUCE, FILLIN.
- Change F_Stop number - 0, 400, 560, 800, 1600.
- Select exposure modes - Preset modes are auto, landscape, snow, beach, sunset, night, fireworks, portrait, backlight, spotlight, sports, text.
- Disable/Enable shutter feedback.
- Exit - Close this MIDlet and return to the initial window.
- Snapshot setting - Set whether to display the snapshot on the screen or print it to a file. Snapshots are stored in:
username\javame-sdk\3.4\work\devicename\appdb\filesystem\root1

Moving Helicopter

Simulates a helicopter (red dot) flying around a stationary observer (blue dot). Use headphones for best results. You can control the parameters of the simulation with the soft menu options: Volume, Location settings, Spectator orientation, and Distance Attenuation settings. After viewing menu options, press the close button (the X on the right) to return to the helicopter scenario.

With the Location settings be aware that supplying large values for the screen width or flight altitude means the helicopter might be out of range - that is, it flies off the screen and you might not be able to hear it.

For spectator orientation stereo headphones or speakers help detect the difference in position, assuming your volume and location settings put the helicopter in audible range. The same is true for the Distance Attenuation settings, which enable you to control the doppler effect.

Running the Demos Sample Project

This demo contains several MIDlets that highlight different MIDP features. Click or use the navigation keys to highlight a MIDlet, then select the Launch soft key.

- "Colors"
- "Properties"
- "Http"
- "FontTestlet"
- "Stock"
- "Tickets"
- "ManyBalls"
- "MiniColor"
- "Chooser"
- "HttpExample"
- "HttpView"
- "PushExample"

Colors

This application displays a large horizontal rectangle that runs the width of the screen. Below, ten small vertical rectangles span the screen. Finally, three horizontal color bars indicate values for blue, green, and red (RGB). Values are expressed as decimal (0-255) or hexadecimal (00-ff) based on the first menu selection.

- To select a vertical bar to change, use the up navigation arrow to move to the color bars. Use the right navigation arrow to highlight a color bar. The large rectangle becomes the color of the selected bar.
- Use the up or down selection arrows to select the value to change (red, green, or blue). Use the left or right arrow keys to increase or decrease the selected value. The second menu item enables you to jump in increments of 4 (Fine) or 32 (coarse).
- You can change the color on any or all of the vertical bars.

Properties

This MIDlet displays your system property values. The output is similar to the following values:

```
Free Memory = 2333444
Total Memory = 4194304
microedition.configuration = "CLDC-1.1"
microedition.profiles = "MIDP-2.1"
microedition.platform = "j2me"
microedition.locale = "en-US"
microedition.encoding = "ISO8859_1"
```

Http

This test application uses an HTTP connection to request a web page. The request is issued with HTTP protocol GET or POST methods. If the HEAD method is used, the head properties are read from the request.

Preparing to Run the Demo

Before beginning, examine your settings as follows.

- Right-click on Demos and select Properties.
 - Select the Running category.
 - Select Regular Execution.
 - Check Specify the Security Domain and select Maximum.
 - Click **OK**.
- If you are using a proxy server, you must configure the emulator's proxy server settings as described in ["Configuring the Web Browser and Proxy Settings."](#) The HTTP version must be 1.1.
- If you run antivirus software, it might be necessary to create a rule that allows your MIDlet to permit connections to and from a specific website. See ["Troubleshooting."](#)

Running the Demo

Launch the Http MIDlet. To test, select the Menu soft key and select Get, Post, or Head to test the selected URL.

Http Test returns the information it obtains. If the information fills the screen use the down arrow to scroll to the end. The amount of information depends on the type of request and on the amount of META information the page provides. To provide body information or content, the page must declare `CONTENT-LENGTH` as described in RFC 2616.

Using Menu Options

Use the **Menu** soft key to select an action. The Menu items vary depending on the screen you are viewing.

- Select **Qwerty** to set the input type. This activates a submenu with the options **Qwerty**, **123**, **Abc**, **Virtual**, and **Symbols**. This choice is present if you have the option to edit a URL (select **Choose**, then click the **Add** soft button).
- Select **GET** or press the **Get** soft key to retrieve data from the selected URI.
- Select **POST** to retrieve the post information from the server handling the selected page.
- Select **HEAD** to retrieve only the META information from the headers for the selected URI.
- Select **Choose** to display the current list of web pages. You can choose a different page or add your own page to the list. To specify a new URL, click the **Add** soft button. The screen displays `http://`. Type in the rest of the URL. If necessary select **Qwerty** on the menu and select a different input method. Be sure to end with a slash (/). For example `http://www.internetnews.com/`. Press the **OK** soft button. The Http Test screen shows your new URL and prompts for an action.

FontTestlet

This MIDlet shows the various fonts available: Proportional, Regular, Regular Italic, Bold Plain, and Bold Italic. Select 1 or 2 from the menu to toggle between the system font (sans serif) and the monospace font.

Stock

Like the Http demonstration, this sample uses an HTTP connection to obtain information. Use the same preparation steps as "**Http**."

Run the Demos project and launch the Stock MIDlet.

By default, the screen displays an empty ticker bar at the top. Below the ticker, the menu list shows four applications: Stock Tracker, What If? Alerts, and Settings. You must add stock symbols before you can use the first three applications.

Add Stock Symbols to the Ticker

To add a stock symbol to the ticker, use the navigation arrows to select **Settings**.

Select **Add Stock**.

The display prompts you to enter a stock symbol. Type `ORCL` and select the **Done** soft key. The stock you added and its current value is now displayed in the ticker. Add a few more stock symbols, such as `IBM` and `HPQ`.

Change the Update Interval

By default the update interval is 15 minutes. Select **Updates** to change the interval. Use the navigation arrows to select one of **Continuous**, **15 minutes**, **30 minutes**, **one hour**, or **three hours**. Select the **Done** soft key.

Remove a Stock

Select Remove a Stock. You see a list of the stocks you have added. Use the navigation keys to select one or more stocks to remove. Select the **Done** soft key.

Stock Tracker

Stock Tracker displays a list of the stocks you added and their current values. Stock tracker displays additional information about the selected stock, for example, the last trade and the high and low values.

Select a stock and press **Select**.

What If?

What If? is an application that asks for the original purchase price and the number of shares you own. It calculates your profit or loss based on the current price.

Select a stock symbol.

Enter the purchase price and the number of shares, then press **Calc**.

Alerts

This application sends you a notification when the price changes to a value you specify.

From the main menu, select **Alerts**.

Select **Add**.

Select a Stock. The screen prompts, "Alert me when a stock reaches". Enter an integer.

The alert is placed on the Current Alerts list. To remove an alert, press Remove and select the alert. Select the **Done** soft key.

When the value is reached you hear a ring and receive a message. For example, *Symbol* has reached your price point of *\$value* and is currently trading at *\$current_value*. When the alert is triggered it disappears from the Current Alerts list.

Tickets

This demonstrates how an online ticket auction application might behave. The home screen displays a ticket ticker across the top. Click Done to continue to the Welcome To Tickets page. The Choose a Band field displays BootWare & Friends by default.

Choose a band from the dropdown menu. The available auction appears.

Select **Make a Bid** from the menu. Use the arrow keys to move from field to field. Fill out each field, then select the **Next** soft key. The application asks you to confirm your bid. Press the Submit soft key or use the arrow keys to highlight Submit then press Select. You receive a Confirmation number. Click **Bands** to return to the Bands page.

Select set an alert, select Set an Alert from the soft Menu. In the bid field type in a value higher than the current bid and click the Save soft key. You are returned to the Choose a Band page. You can trigger the alert by making a bid that exceeds your alert value. Your settings determine how often the application checks for changes, so the alert may not sound for a few minutes.

To add a band to the Choose a Band dropdown list, select the Menu soft key and select Add Bands. Type in a band name or a comma-delimited list of names. Select the Save soft key. After confirmation you are returned to the Welcome To Tickets page. The added band(s) are displayed after the Choose a Band drop-down menu.

Note, this is only a demonstration. To fully describe the band you must edit the following file:

`username\My Documents\NetBeansProjects\Demos\src\example\auction\NewTicketAuction.java`

To remove a band, click the **Menu** soft key and select Remove Bands. Check a box for one or more bands. Select the **Save** soft key.

To display the current settings for ticker display, updates, alert volume, and date, select the **Menu** soft key and select 6. If desired, use the arrow keys and the select key to change these values. Select the **Save** soft key.

ManyBalls

This MIDlet starts with one ball traveling the screen. Use the up and down arrows to accelerate or decelerate the ball speed (fps). Use the right or left arrows to increase or decrease the number of balls.

MiniColor

This MIDlet sets an RGB value. Use navigation keys to change color values.

Keyboard controls work as you would expect. First cursor up or down to highlight a color, and then use left and right keys to lower and raise the value of the selected color.

Chooser

The Chooser application uses a variety of controls to change text color, background color, and fonts.

- Select **Menu > Text Color**. Change the color as described in the ["MiniColor"](#) and select the OK soft button.
- Select Menu **Menu > Background Color**. Change the color as described in the ["MiniColor"](#) and select the OK soft button.
- Select **Menu > Fonts**. Change the font face, style, and size using the navigation and selection buttons to move through the font options.

Cursor up and down to highlight a property, then select. The left and right keys jump between lists. Up and down keys move item by item.

Click **OK** to continue.

HttpExample

This sample makes an HTTP communication. A popup confirms the transaction was successful.

HttpView

This application displays three predefined URLs.

Select a URL, and press the soft buttons to cycle through Head, Headers, Requests, and Errors.

Alternatively, Use the menu options.

PushExample

This application simulates a feed. As soon as you connect, you receive and display a graphic. Select **Done** to continue.

Running FPDemo

FPDemo is a simple floating point calculator.

1. Enter a number in the first field.
2. To select an operator, highlight the drop-down list and click to select. Cursor down to highlight an operator, then click to make a selection.
3. Enter a second value.
4. From the Menu, select Calc or select 2 to calculate the result.

Running Games

This application features three games: TilePuzzle, WormGame, and PushPuzzle.

TilePuzzle. The desired result, "Rate your mind pal" is shown first. From the soft Menu, select 1, Start. The scrambled puzzle is displayed. The arrow keys move the empty space, displacing tiles accordingly (the arrow key indicates which tile to swap with the space). From the menu you can Reset, or change options.

WormGame. From the soft Menu, select 1, Launch. Use the arrow keys to move the worm to the green box without touching the edge of the window. When the game is launched, use the soft menu to change game options.

PushPuzzle. Use the blue ball to push the orange boxes into the red squares in the fewest number of moves.

Running Network Demo

This demo has two MIDlets: Socket Demo and Datagram Demo. Each demo requires you to run two emulator instances so that you can emulate the server and client relationship. For example, run the demo on JavaMEPhone1 and JavaMEPhone2.

Socket Demo

In this application one emulator acts as the socket server, and the other as the socket client.

1. In the first emulator, launch the application, then select the Server peer. Select Start. The Socket Server displays a status message that it is waiting on port 5000.
2. In the second emulator, launch the application, select the Client peer, then select Start. Select Start to launch the client. The Socket Client displays a status message that indicates it is connected to the server on port 5000. Use the down navigation arrow to highlight the Send box. Type a message in the Send box, then select the Send soft key.

For example, in the client, type `Hello Server` in the Send box. Select Send from the menu. The server emulator activates a blue light when the message is received.

3. On the emulator running the Socket Server, the status reads: `Message received - Hello Server`. You can use the down arrow to move to the Send box and type a reply. For example, `Hello Client, I heard you`. From the menu, select Send.
4. Back in the Socket Client, the status is: `Message received - Hello Client, I heard you`. Until you send a new message, the Send box contains the previous message you sent.

Datagram Demo

This demo is similar to Socket Demo. Run two instances of the emulator. One acts as the datagram server, and the other as the datagram client.

1. In the first emulator, launch Datagram Demo, then select the Server peer. Select Start. Initially, the Datagram Server status is `Waiting for connection on port 5555`, and the Send box is empty.
2. In the second emulator, launch Datagram Demo, select the Client peer, ensure the port number is 5555 and select Start. The Datagram Client status is: `Connected to server on port 5555`. Use the down navigation arrow to highlight the Send box. Type a message in the Send box, then select the Send from the menu. For example, type `Hello datagram server`. From the menu, select Send.
3. On the emulator running the Datagram Server, the status displays: `Message received - Hello datagram server`. You can use the down arrow to move to the Send box and type a reply to the client.
4. In the Datagram Client, the status field displays the message received from the server. The Send box contains the last message you sent. Overwrite it to send another message.

Running PhotoAlbum

The PhotoAlbum demo displays both static and animated images. When you are displaying an image, you can use the Options soft menu to change the borders. If the image is animated, you can change the speed of the playback.

Running UIDemo

UIDemo showcases a variety of MIDP user interface element implementations. Most elements have some interactive capability (navigate and select) and some allow keypad or keyboard input.

Input interaction is similar across demos. You can select items from lists or type in data.

This demo implements three list selection methods:

- Exclusive (radio buttons)
- Multiple (check boxes)
- Pop-Up (a drop list).

When entering data, you can use the soft menu to apply one of the following input types to text boxes and fields (note, some elements do not use all input types). When a field is selected, the soft Menu label displays `Qwerty`. Open the menu and you see the input types numbered 1 through 5.

1. **Qwerty**. Any character on the keyboard
2. **123**. Any numeral
3. **ABC**. Any letter
4. **Predict**. Predicts next character based on prior input
5. **Symbols**. Opens a list of symbols; click to make a selection.
6. **Virtual**. Click keys on a virtual keyboard to enter data.

The Qwerty, 123, and ABC categories act as filters. For example, if you assign 123 to a field and you type "abc", nothing is entered in the field.

When you finish a demo, select the home button to return to the UIDemo launch page:

Figure 4–6 The Home Button



CustomItem. This demo features text fields, and text fields in table form. To type in the table, select a cell, then click to open a text entry panel and type your input. From the menu, select OK.

StringItem. Displays labels, a hyperlink, and a button. The soft menu action varies depending on the selected element.

Gauge. Interactive, non-interactive, indefinite and incremental gauges.

Alert. Uses pop-ups to display alerts. Set the alarm type and the length of the timeout from drop lists. Select the alert type and select the Show soft button.

ChoiceGroup. Radio buttons, check boxes, and pop-ups on one screen.

List. Select exclusive, implicit, or multiple to display the list type on a subsequent screen.

TextBox. Use text fields, radio buttons, check boxes, and pop-ups. Select a text box type and press the Show button.

TextField. Text fields with the six input types.

DateField. Set date and time using drop lists.

Ticker. A scrolling ticker.

Running IMP-NG Sample Projects

This section describes how to use demos created specifically for the IMP-NG platform (see "IMP-NG"). Because IMP-NG is headless the only user interface is to observe application status in the emulator's external events generator, or in the Output window (or the console if you execute the demo from the command line).

With the exception of I2CDemo, the sample projects in this section can be run on the emulator or on an external device.

See the Oracle® Java ME Embedded Getting Started Guide for the Windows Platform. These documents are available on the Java ME documentation site at:

<http://docs.oracle.com/javame/embedded/embedded.html>

Expand the Oracle Java ME Embedded *Version* node and then the Getting Started and Release Notes node.

Running the GPIODemo

This demo can be run on an emulator or an external device. The implementations are different, as the emulator uses the external events generator, and the external device supports direct interaction.

Running the GPIODemo on the Emulator

1. Run GPIO demo on an IMP-NG emulator.
2. Click the GPIO Pins tab. This view approximates the device actions.
3. Click the Tools menu and select External Events Generator to open the external events generator, and click the GPIO tab. A single click on a button turns on LEDs indicating the button pushed and the pin affected. This information is also written to the Output window.

Beneath each pin you can click the blue wave button to open the wave generator. The wave generator simulates the frequency and duration of the signal to the LED.

4. Pressing pin BUTTON 2 in the external events generator changes the state of the pin named LED 5. The button value "Low" corresponds to the LED value "High" and vice versa.
5. Pressing pin BUTTON 3 changes the state of the port named "LEDS." Consequently pins bound to this port (LED 1, LED 2, LED 3, LED 4) in the following way:
 - If the BUTTON 3 state is "High" the port value is set to 0 and all bound pins are set to "Low."
 - If the BUTTON 3 state "is Low" and the BUTTON 2 state is "Low," the port value is set to 2 and the pins are set to the following state:
LED 1 - Low, LED 2 - High, LED 3 - Low, LED 4 - Low
 - If the BUTTON 3 state "Low" and the "BUTTON 2" state is "High," the port value is set to 3 and the pins are set to the following states:
LED 1 - High, LED 2 - High, LED 3 - Low, LED 4 - Low

Running the GPIODemo on the Reference Board

The buttons are wired by GPIO. Assuming that you are looking at the board and the Reset button is on the bottom left:

- Reading from left to right, the LEDs are labeled: PH.3, PH.6, PH.7, PI.10, PG.6, PG.6, PG.8, and PH.2
- The buttons, from left to right, are Reset, Wakeup, Tamper, and User.
The Wakeup button corresponds to PH.3 (Listener 1 Pin 5)
The Tamper button corresponds to PG.6 (Listener 2 Pin 6).
The User button corresponds to PH.3 and PI.10 (Listener 3 Pin 7)
- Pressing Tamper turns on the light (PG.6), and releasing turns off the light
- Pressing the User button when the Tamper button is released turns on lights on for LEDs PH.3 and PH.6.
- Pressing the User button when the Tamper button is pressed (and as a result the light on LED PG.6 is on) turns on light on LED PH.3 only.
- Releasing the User button turns the lights off on LEDs PH.3 and PH.6.

Running the I2CDemo

This demo is designed to work with the IMP-NG runtime for Windows. It has no user interaction.

- Launch the I2C demo.
- In the emulator, click the I2C tab.

The demo acquires a slave named I2C_Echo, writes data to the slave, and retrieves it. The demo is successful if the Sent Data and Received Data matches.

Running the NetworkDemoIMPNG

This demo is a headless version of "[Socket Demo](#)."

You can configure this demo as a server or as a client by editing the application descriptor. You launch two instances of this demo, the first one acts as a server and the second one acts as a client. The client instance attempts to connect to the server instance and if the connection is successful they exchange a message.

Running NetworkDemoIMPNG on the Emulator

1. Create two instance projects of the NetworkDemoIMPNG sample project.
2. Right click the first project and select Properties.
3. In the Platform category select the device IMPNGDevice1. In the Application Description category set the value of the following property:

```
Oracle-Demo-Network-Mode:Server
```
4. Click OK.
5. Launch the first project. It opens on the emulator IMPNGDevice1 and waits for a connection. You should see messages like the following:
6. Right click the second project and select Properties.
7. In the Platform category select the device IMPNGDevice2. In the Application Description category set the value of the following property:

```
Oracle-Demo-Network-Mode:Client
```
8. Click OK.
9. Launch the second project. It opens on the emulator IMPNGDevice2.
10. The client attempts to connect to the server. If successful, you see the following in the output tab of the first project (the server):

```
Waiting for connection on port 500
[AMS-TRACE] MIDlet:NetworkDemoIMPNG status=2
[AMS-TRACE] MIDlet:NetworkDemoIMPNG status=1
Connection accepted
Message received - Client messages
```

The output of the second project (the client) shows the following:

```
[AMS-TRACE] MIDlet:NetworkDemoIMPNG status=2
[AMS-TRACE] MIDlet:NetworkDemoIMPNG status=1
Connected to server localhost on port 500
Message received - Server string
```

Running NetworkDemoIMPNG on the Reference Board

You can run one of the instance projects on the board and the other in one of the emulators. Follow these steps to run the client on the board and the server in one of the emulators:

1. Right click on the first project (the server) and select Properties. In the Platform category select the device IMPNGDevice1 (the emulator) and click OK. In the Application Description category set the value of the property Oracle-Demo-Network-Mode to **Server** and click OK.
2. Launch the first project (the server). It runs on the emulator and waits for a connection.
3. Right click on the second project (the client) and select Properties. In the Platform category select the device IMPNGExternalDevice1 (the board). In the Application Description category set the value of the property Oracle-Demo-Network-Mode to **Client** and click OK.

In the Application Descriptor category set the value of the property Oracle-Demo-Network-Address to the IP address of the computer where Eclipse is running and click OK.

4. Launch the second project (the client). It runs on the board and attempts to connect to the server. If successful, you see the following in the output tab of the first project (the server):

```
Connection accepted
Message received - Client messages
```

The TCP log of the board (the client) shows the following:

```
Connected to server 10.0.0.10 on port 5000
Message received - Server String
```

Running the PDAPDemoIMPNG

This demo is a headless version of the PDAPDemo file browser.

Running the PDAPDemoIMPNG on the Emulator

Follow these steps to run the demo on the emulator:

1. Create test files and directories inside the emulator's file system:
`\username\javame-sdk\3.4\work\IMPNGDevice1\appdb\filesystem\root1`
2. Load the project in the Package window.
3. In the Platform category, select the device IMPNGDevice1 and click **OK**.
4. In the Device Selector window, right-click an IMPNGDevice1 emulator.
5. Select **Run Project > PDAPDemoIMPNG** from the context menu.
6. Launch the project.
7. On the emulator, click the **Tools** menu and select **Manage File System** to see a list of mounted file systems.
8. Open a terminal emulator and create a Telnet connection to localhost on port 5001.

Note: The Telnet negotiation mode must be set to Passive. The negotiation mode can be set inside a Telnet client application (for example, PuTTY), by choosing Category --> Connection --> Telnet --> Passive.

9. A command line opens where you can browse the emulator's file system. You can use the following commands:
 - `cd` - change directory
 - `ls` - list information about the FILES for the current directory
 - `new` - create new file or directory
 - `prop` - show properties of a file
 - `rm` - remove the file
 - `view` -View a file's content

Running PDAPDemoIMPNG on the Reference Board

Follow these steps to run the demo on the reference board:

1. Right-click the project and select Properties. In the Platform category, select the device `IMPNGExternalDevice1` and click **OK**.
2. Launch the project. It runs on the reference board.
3. Open a terminal emulator and create a raw connection to the IP address of the board on port 5001.
4. The command line that opens is the same as the one you use when you run the demo on the emulator.

The file system of the demo is stored in the directory `java/IMletID` inside the SD card, where *IMletID* is a number that the AMS assigns to an IMlet during its installation.

Running the Pulse Counter (Data Collection) Demo

Pulse counting is the process of sending an electronic pulse to a counter, and then tracking them (via a timestamp) when they arrive. To observe this process, run the following demo on your IMPNG device, using the External Events Generator and the Pulse Counters tab:

1. Launch the Data Collection Demo.
2. In the Device Selector, right-click the `IMPNGDevice1` emulator and select Run JAR or JAD.
3. In the file browser, navigate to and select the Data Collection demo JAD file. For example:

```
installdir/apps/DataCollectionDemo/dist/DataCollectionDemo.jad
```

4. When the emulator opens with `DataCollectionDemo` installed, select `DataProcessorIMlet` and `PulseCounterImlet` and click **Run**.
5. Click **OK** twice (once for each IMlet) in the Run IMlet dialog box.
You do not have to select the debugger, profiler, or memory monitor tool.
6. Open the External Events Generator by clicking the **Tools** menu and selecting **External Events Generator** or clicking the External Events Generator icon.
7. Click the Pulse Counters tab.
8. Observe Output Console in the IDE as you click **Send Pulse** for the first counter, `COUNTER_PA0`.

Alternatively, you can select **View > Output Console** in the emulator menu to open the Output Console window.

Figure 4–7 Output Console Window Showing Pulse Counter Output

```

DataCollectionDemo.jad (IMPNGDevice1) x | DataCollectionDemo (run) x |
ProtocolClient is OK.
Starting PulseCounterListener...
PulseCounterListener start is OK.
[AMS-TRACE] MIDlet:DataCollectionDemo status=2
Feb 25 11:49:20 global com.oracle.mee.datacollection.sample.dataprocessor.DataH:
INFO Data: Pulses timestamp = Mon Feb 25 11:49:20 GMT-08:00 2013 value = 0
[AMS-TRACE] MIDlet:DataCollectionDemo status=1
Feb 25 11:49:51 global com.oracle.mee.datacollection.sample.dataprocessor.DataH:
INFO Data: Pulses timestamp = Mon Feb 25 11:49:51 GMT-08:00 2013 value = 1
Feb 25 11:50:06 global com.oracle.mee.datacollection.sample.dataprocessor.DataH:
INFO Data: Pulses timestamp = Mon Feb 25 11:50:06 GMT-08:00 2013 value = 2

```

A pulse timestamp is output for each click of **Send Pulse**.

Configuring a Pulse Counter

You can configure a pulse counter for an IMPNG device. You can also create a custom IMPNG device with pulse counter capabilities. To do this, follow these steps:

1. Go to **Tools > Java ME > Custom Device Editor**.
For Eclipse users, go to **Run > Custom Device Editor**.
2. Select IMP-NG in the Custom Device Editor window and click **New...**
3. In the New IMP-NG Device dialog box, specify a name for the custom device, for example, IMPNGCustomDevice1.
4. (Optional) you can provide a brief description such as emulator with pulse counter.
5. Click the Pulse Counters tab.
6. Click Add for the number of pulse counters you want. For example, click **Add** four times to create pulse counters with IDs of 0, 1, 2, and 3.
IDs are automatically assigned to each pulse counter. To unassign an ID, select the row of the desired pulse counter and uncheck the Assign ID option. The unassigned pulse counter is moved to the top of the list.
7. For each pulse counter, click in the Type column and select the signal trigger type: Falling Pulse Edge, Negative Edge Pulse, Rising Pulse Edge, or Positive Edge Pulse.
8. Click OK.

You also have the option to bind a pulse counter to an existing GPIO input pin by selecting the specific pin from the dropdown list in the Input Pin column.

The pulse counter type should conform to the trigger value of the binding input GPIO pin. This means that:

- Pulse counters of the type Falling Pulse Edge can only be bound to input pins with the Falling Edge trigger.

- Pulse counters of the type Rising Pulse Edge can only be bound to input pins with the Rising Edge trigger.
- Pulse counters of the type Negative Pulse Edge or Positive Pulse Edge can only be bound to input pins with the Both Edges trigger.

Running the Light Tracker Demo

The Light Tracker demo is specifically aimed at showing off functionality on an embedded device, such as the Keil MCBSTM32F200 reference platform.

In this demo, a certain number of LEDs are turned on and turned off on the board, in a sequence that you can control. It makes use of the Device Access API and the GPIO Port to demonstrate its functionality. It requires connection of an ADC channel to an on-board potentiometer.

For more information on the setup of the Light Tracker demo, see the `LightTrackDemo readme.txt` file, in the location where you have installed the Oracle Java ME SDK sample applications. For example:

```
C:\Documents and Settings\username\Java_ME_SDK\samples\LightTrackDemo
```

For more information on the Keil MCBSTM32F200 platform, see the *Oracle Java ME Embedded Getting Started Guide for the Reference Platform (Keil)*.

Running the System Controller Demo

The System Controller demo is specifically aimed at showing off functionality on an embedded device, such as the Keil MCBSTM32F200 reference platform.

The purpose of this demo is to control the lifecycle of IMlets on the reference platform. It makes use of the following functionalities:

- Multitasking Virtual Machine (MVM)
- IMlet auto-start
- Application Management System (AMS) API
- Logging API
- Device Access API
- General Purpose Input/Output (GPIO)
- Watchdog timer

For more information on the setup of the System Controller demo, see the `SystemControllerDemo readme.txt` file, in the location where you have installed the Oracle Java ME SDK sample applications. For example:

```
C:\Documents and Settings\username\Java_ME_SDK\samples\SystemControllerDemo
```

For more information on the Keil MCBSTM32F200 platform, see the *Oracle Java ME Embedded Getting Started Guide for the Reference Platform (Keil)*.

Creating and Editing Projects

A project is a group of files comprising a single application. Files include source files, resource files, XML configuration files, automatically generated Apache Ant build files, and a properties file.

When a project is created, the SDK performs these tasks:

- Creates a source tree you can examine in the ["Working With Projects"](#) or ["View Project Files."](#)
- Sets the emulator platform for the project.
- Sets the project run and compile-time classpaths.
- Creates a build script that contains actions for running, compiling, debugging, and building Javadoc. Project properties influence the build process, as described in ["Building a Project."](#) See also ["Build a Project from the Command Line."](#)

Oracle Java ME SDK and NetBeans create their project infrastructure directly on top of Apache Ant. Oracle Java ME SDK projects can be opened and edited in NetBeans, and vice-versa. With the Ant infrastructure in place, you can build and run your projects within the SDK or from the command line.

The SDK provides two views of the project:

- The Projects window provides a logical view of the project.
- The Files window displays a physical view of the project.

Project settings are controlled in the project Properties window. Typically, you right-click on an item or subitem in a tree (a project, a file, or a device) and select Properties.

Project Types

The MIDP/CLDC platform implements the Mobile Information Device Profile and Connected Limited Device Configuration (JSRs 118 and 139). As described in ["IMP-NG,"](#) the IMP-NG platform is a type of CLDC platform.

The CDC platform is implemented to support Advanced Graphics and User Interface Optional Package for the J2ME Platform, Personal Basis Profile 1.1, and the Connected Device Configuration (JSRs 209, 217 and 218). The AGUI API combines the PBP API and a subset of Java Platform, Standard Edition (Java SE) Swing capabilities.

MIDP Projects

A MIDP application (a MIDlet), is deployed as a MIDlet suite. A MIDlet suite is distributed as a Java archive (JAR) file and a Java Application Descriptor (JAD) file.

The IMP-NG version of a MIDlet is an IMlet. However, because IMP-NG is a subset of CLDC you can write IMP-NG applications as MIDlets.

The JAR file includes the Java classes for each MIDlet in the suite, Java classes shared between MIDlets, resource files, and other supporting files. The JAR file also includes a manifest describing the JAR contents and specifying attributes the Application Management Software (AMS) uses to identify and install the MIDlet suite.

The JAD file contains attributes that allow the AMS to identify, retrieve, and install the MIDlets in a project. The SDK automatically creates JAD and JAR files when you build the project.

CDC Projects

The CDC platform is implemented to support Advanced Graphics and User Interface Optional Package for the J2ME Platform, Personal Basis Profile 1.1, and the Connected Device Configuration (JSRs 209, 217 and 218). The AGUI API combines the PBP API and a subset of Java Platform, Standard Edition (Java SE) Swing capabilities.

Oracle Java ME SDK version 3.4 supports CDC projects running as standalone applications. The CDC project structure and behavior are much the same as that of CLDC projects.

Note: An Xlet cannot be run standalone. It depends upon an application manager to manage its life cycle (its state) and system services. Xlets are not supported in this release.

A standalone CDC project requires a main application class that includes a method named `main()` that handles class loading, object creation, and method execution. The application interacts directly with the Java Runtime Environment to manage its own life cycle and system resource needs. When the `main()` method exits, the standalone application terminates.

The Project Wizard

This section describes how to use the Project Wizard to create Java ME projects. The project provides a basic infrastructure for development. You provide source files, resource files, and project settings as needed. Most project properties can be edited later. For more on project properties, see [Chapter 6, "Viewing and Editing Project Properties."](#)

Create a MIDP Project

Follow these steps to create a MIDP project.

1. Click the **File** menu and select **New Project**.

The New Project wizard opens.

2. In the New Project window, select the Java ME category, and the Mobile Application project type. Click **Next**.
3. On the Name and Location page, specify a project name.

Most of the form is auto-filled, but you can alter any of the editable fields.

Checking Create Default Package and Main executable Class creates a sample package and main class for your application. Click **Next**.

4. On the Default Platform Selection page, select the Oracle Java(TM) Platform Micro Edition SDK 3.4 platform.

The platform determines which devices you see in the Device dropdown menu.

5. Make a device selection.

The selected device typically determines the Device Configuration. If more than one Device Profile is available, make a selection. Click **Finish**.

The new project is listed in the Projects pane.

Note: You can make additional project configurations using project configuration templates from previously saved templates or from templates installed on the platform by clicking Next on the Default Platform Selection page.

Create an IMP-NG Project

The process for creating an IMP-NG project is almost the same as a CLDC project. There are just a few things to watch for.

1. Click the **File** menu and select **New Project**.

The New Project wizard opens.

2. In the Choose Project window, select the Java ME category, and the Mobile Application project type. Click **Next**.

3. On the Name and Location page, specify a project name. Most of the form is auto-filled, but you can alter any of the editable fields.

Checking Create Default Package and Main executable Class creates a sample package and main class for your application. Click **Next**.

4. On the Select Platform page, change the platform selection to Oracle Java(TM) Platform Micro Edition SDK 3.4. The platform determines which devices you see in the Device dropdown menu.

Select an IMP-NG device, and select a Device Profile.

Click Finish.

5. To run the new project follow the steps in ["Running a Project."](#)

Create a CDC Project

NetBeans provides a wizard for creating new projects quickly and easily. Most project properties can be edited later on.

1. Click the **File** menu and select **New Project**.

The New Project wizard opens.

2. In the Categories window select Java ME and in the Projects window select CDC Application.

3. On the Name and Location page, specify a project name. Most of the form is auto-filled, but you can alter any of the editable fields.

Check the Create Main class option to insert a template of the class Main in your project. You can rename the class or accept the default name. Click **Next**.

4. On the Select Platform page, change the platform selection to CDC Oracle Java(TM) Platform Micro Edition SDK 3.4. The platform determines which devices you see in the Device dropdown menu.

Select a CDC device and a Device Profile, then click **Finish**.

5. To run the new project follow the steps in ["Running a Project,"](#) except you can select your new project instead of a sample project.

Import a Legacy MIDP Project

If you created a project using the Sun Java Wireless Toolkit for CLDC on Windows or Linux you can import your MIDlets into Oracle Java ME SDK projects. You can also use this procedure to create a project based upon a legacy sample project.

1. In the **File** menu, select **New Project**.
2. In the New Project dialog box, be sure Java ME is selected and select Import Wireless Toolkit Project. Click **Next**.
3. Specify the WTK project location.
Use browse to open the directory containing the legacy project.
4. Select a project and click **Next**.
5. Provide the project name, location, and folder for the new project.
The default name, project name and folder name are based on the name of the project you are importing. Click **Next**.
6. Select the platform type, the default device, and the configuration and profile, if applicable. Click **Finish**.
Your new project opens in the Projects window.
7. If the legacy project used signing, you must configure the signing properties as described in ["Managing Keystores and Key Pairs."](#)

Import a Legacy CDC Project

If you created a project using the CDC Toolkit, you can import your applications into Oracle Java ME SDK projects. You can also use import to create a project based upon a sample project.

Note: Standalone projects created in the CDC Toolkit can be imported. Xlets cannot be imported.

The CDC platform name for the Oracle Java ME SDK version 3.4 does not match the legacy platform name in the CDC Toolkit 1.0 and the CDC Mobility Pack. Consequently, you get a reference error when you import a legacy CDC project.

Note: To avoid the reference error, create a platform with the legacy name, as described in ["Create a Platform for Legacy CDC Projects."](#) You only need to create the platform once.

1. In the **File** menu, select **New Project**.

2. In the New Project dialog box, be sure Java ME is selected and select Import CDC Toolkit Project. Click **Next**.
3. Browse to select the project location.

The wizard detects any applications in the legacy installation and displays their locations on disk. Select a project and click **Next**.

4. Provide the Project Name, Location, and Folder for the new project. Note that the default name project name and folder name are based on the name of the project you are importing. Click **Finish**.

The imported project opens in the Projects window.

See ["Create a Platform for Legacy CDC Projects"](#) and ["View Project Files."](#)

Working With Projects

The logical view of the project, shown in the Projects window, provides a hierarchy of sources and resources. Right-click on the project node to see actions related to the project.

New. Opens a form to build a new object for the current project. The new object is placed in the project's file structure by default, but you can control the file name and location. The **Other** option in the **New** menu permits adding different types of files to the project. For a sample procedure, see ["Generating Stub Files from WSDL Descriptors."](#)

Build. Builds a distribution Java archive (JAR) file. Project properties control the build process as described in ["Building a Project."](#)

Clean & Build. Cleans, then builds a distribution JAR file.

Clean. Cleans the build files.

Generate Javadoc. See the online help topic [Generating Javadoc Documentation](#).

Deploy. See the online help topic ["Deploying Java ME Applications."](#)

Batch Build..., Batch Clean & Build..., Batch Clean..., Batch Deploy... See the online help topic ["About Java ME MIDP Projects."](#)

Run. Runs the project with the default device, as specified on the Platform property page. See ["Platform Selection."](#)

Run With... Run the selected project with a device you choose. This option can override the default device specified in the project properties.

Debug. See the online help topic ["Debugging Tasks: Quick Reference."](#)

Profile. Attach the profiler to the selected project. See [Chapter 9, "Profiling Applications."](#)

Set as Main Project. Make the current project the new main project. Toolbar actions, such as clicking the green Run button, act upon the main project by default.

Unset as Main Project. This option is visible if the selected project is the main project.

Open Required Projects. Open any projects that the current project requires.

Close. Close the current project. Be sure that any processes are stopped, as closing a project might not stop the emulator.

View Project Files

The Files window displays a physical view of all project files. Right-click to view project properties or select an action related to the project.

build. The output directory for the compiled classes listed below. This directory also contains `manifest.mf`, the manifest file that is added to the JAR file.

- `compiled`. Contains all compiled classes.
- `obfuscated`. Holds the obfuscated versions of the class files.
- `preprocessed`. Holds the source files after they are preprocessed. The files differ from the original source files if you are using project configurations.
- `preverified`. Holds the preverified versions of the class files. These files are packaged into your project's distribution JAR.
- `preverifysrc`. Versions of the source files before they are preverified.

dist. The output directory of packaged build outputs (JAR files and JAD files). The `dist` directory also contains generated Javadoc documentation.

lib. Contains libraries you have added to the project. See ["Adding Libraries and Resources."](#)

nbproject. The directory that contains the project Ant script and other metadata. This directory contains the following files:

- `build-impl.xml`. The SDK-generated Ant script. Do not edit `build-impl.xml` directly. Always override its targets in `build.xml`.
- `private/private.properties`. Properties that are defined for you alone. If you are sharing the project, any properties you define in this file are not checked in with other project metadata and are only applied to your SDK installation.
- `project.properties`. Ant properties used to configure the Ant script. This file is automatically updated when you configure the project's properties. Manual editing is possible, but it is not recommended.
- `project.xml` and `genfiles.properties`. Generated metadata files. It is possible to edit `project.xml` manually, but it is not recommended. Do not edit `genfiles.properties`.

res. Resource files you have added to the project. See ["Adding Libraries and Resources."](#)

src. Project source files.

build.xml. The build script. This build script only contains an import statement that imports targets from `nbproject/build-impl.xml`. Use the `build.xml` to override targets from `build-impl.xml` or to create new targets.

See ["Create a MIDP Project"](#) and ["Create a CDC Project."](#)

Create a New MIDlet

To create a new MIDlet from the Files view, right-click a project and select **New > MIDlet**. With this form you can specify the name of the MIDlet and its location within the selected project.

MIDlet Name. The name that users see when the application runs on a device.

MIDlet Class Name. The name of the new MIDP class.

MIDlet Icon. The path to an icon associated with the MIDlet. Users see the icon when the application runs on a device.

Project. Displays the name of the project.

Package. Specifies the location of the MIDlet class in the package hierarchy. You can select an existing package from the drop down menu, or type in the name of a new package. The new package is created along with the class.

Created File. Displays the name and the location of the MIDlet in the system's hierarchy.

When the new MIDlet is created the SDK automatically adds it to the project's Application Descriptor File.

Add Files to a Project

For all projects, right-click to use the context menu to add files to a project. Using this method places files in the proper location in project source or resources.

To add a MIDlet, Java class, Java package, Java interface or Other files, right-click the project name or the Source Packages node, select New, and select the file type.

To add files by format (Project, JAR, Folder, Library) right-click the Resources node and select a format. See "[Adding Libraries and Resources](#)."

It is possible to add files by copying them directly to the project directory but it is not recommended.

Search Project Files

To search a project's files, right-click on the project and select **Find...** . The Find in Files utility supports searching a project's file contents or file names. The search input fields supports simple text matching and regular expressions.

Containing Text. The string you are looking for. If File Name Patterns is empty, all files are searched.

File Name Patterns. The files you are searching in. If the Containing Text field is empty you get a listing of files that match the pattern.

Debugging MIDP and IMP-NG Projects

Java ME Projects use standard NetBeans debugging utilities. Refer to the NetBeans help topic, *Debugging Tasks: Quick Reference*. This topic includes links to a variety of debugging procedures.

If you have an external device that runs a supported runtime you can perform on-device debugging. The device must be detected by the Device Selector, as described in "[Adding an External Device](#)."

Viewing and Editing Project Properties

All projects have properties. Some properties, such as the project's name and location cannot be changed, but other properties can be freely edited as work on your project progresses.

To view or edit a project's properties, right-click the project node and select **Properties**. In the resulting window, you can view and customize the project properties. See the following topics:

- ["General Project Properties"](#)
- ["Platform Selection"](#)
- ["Editing Application Descriptor Properties"](#)
- ["Building a Project"](#)
- ["Running Settings"](#)

General Project Properties

To view the General property page, right-click a project, click **Properties**, and select the General category. The general properties page displays basic project properties. You can set application versioning here, but all other values cannot be edited.

The project name, folder, and source location are set when the project is created. The Application Version Number field displays the version number of the current build.

Application Versioning

The Application Version Counter field displays the next version number to be used. The default advance is 0.0.1. To advance the number beyond this, use the dropdown menu to select a new digit, or enter the value into the field. For example, changing the value to 3 results in a build number of 0.0.3. Changing the value to 100 results in the version number 0.1.0.

Required Projects

This area displays projects you have added to this project. It might be a dependent project or an external library. See ["Adding Libraries and Resources."](#)

Platform Selection

An emulator platform simulates the execution of an application on one or more target devices. To view this property page, right-click a project and click **Properties** and select the Platform category.

Select a platform type from the dropdown menu.

For the emulator platform, be sure to select the 3.4 platform. You might have to use the dropdown menu to ensure the right version is selected.

By default, the devices in the device menu are also suitable for the platform type and emulator platform. The device you select is the default device for this project. It is used whenever you use the Run command. Your device selection influences the Device Configuration and Device Profile options, and the available optional packages.

Be sure that a Device Profile is selected, and select the optional packages you want to include in this project. The selected APIs are automatically added to the project's classpath. See ["Create a MIDP Project."](#)

Editing Application Descriptor Properties

To view this property page, right-click on a project, select Properties, and select the Application Descriptor category. The Application Descriptor properties page enables adding, editing, or deleting project attributes.

CDC Attributes

To view this property page, right-click on a CDC project and select Properties. Select the Application Descriptor category.

Application Name. The display name of the application on the target device.

Application Vendor. The company name or author name for the application.

Description. A concise description of the application.

Detail Description. A detailed description of the application.

MIDP Attributes

To view this property page, right-click on a MIDP project and select Properties. Select the Application Descriptor category, and select the Attributes tab.

The General Attributes table lists the attributes currently contained in the JAD and JAR manifest files:

Type. Lists whether the attribute is required or optional. Custom attributes for passing parameters to the MIDlet using the JAD are also available.

Name. The name of the attribute.

Value. The values for each attribute.

To avoid errors in verification:

- Define all required attributes.
- Do not begin user-defined attribute keys with MIDlet- or MicroEdition-.

Add an Attribute

Follow these steps to add an attribute.

1. Click **Add...** to open the Add Attribute window.
2. Select an attribute from the Name combo box, or delete the current entry and add your own custom entry.

Note: Remember that user-defined attribute names must not begin with `MIDlet-` or `MicroEdition-`.

3. Enter a value for the attribute.
4. Click **OK**.

Edit an Attribute

1. Select an attribute.
2. Click **Edit...** to open the Edit Attribute window.
3. Enter a value for the attribute.
4. Click **OK**.

API permissions, Push Registry Entries, and API Permissions have their own property pages.

Remove an Attribute

Select an Attribute and click Remove to delete it from the list.

MIDlets

To view this page, right-click a project and select Properties. Select the Application Descriptor category, and select the MIDlets tab.

The MIDlets table lists the MIDlets contained in the suite and the following properties:

Name. The displayable name of the MIDlet that the user sees when the MIDlet is run on a mobile device.

Class. The Java class for the MIDlet.

Icon. An icon (a .png file), representing the MIDlet that the user sees when the MIDlet is run on a mobile device.

Add a MIDlet

1. Click **Add...** to open the Add MIDlet window.
The window lists the MIDlets available in the project.
2. Enter a name, then select a MIDlet class from the dropdown menu.
You can also select an icon for the MIDlet from the MIDlet icon dropdown menu.
3. Click **OK**.

Edit a MIDlet

1. Select a MIDlet.
2. Click **Edit...** to open the Edit MIDlet window.
3. Enter a value for the attribute.
4. Click **OK**. The revised values are listed in the table.

Remove a MIDlet

Select a MIDlet and click Remove to delete it from the list.

Change MIDlet Display Order

The list order determines the order in which the MIDlets are displayed.

Select a MIDlet and select **Move Up** or **Move Down** to change its position.

Push Registry

To view this page, right-click on a project and select Properties. Select the Application Descriptor category, and select the Push Registry tab.

Add a Push Registry Entry

1. Click **Add...** to open the Add Push Registry window.
2. Enter Class Name, Sender IP, and Connection String values.
 - **Class Name.** The MIDlet's class name.
 - **Sender IP.** A valid sender that can launch the associated MIDlet. If the value is the wildcard (*), connections from any source are accepted. If datagram or socket connections are used, the value of Allowed Sender can be a numeric IP address.
 - **Connection String.** A connection string that identifies the connection protocol and port number.
3. Click **OK**.

The new values are listed in the table. A push registration key is automatically generated and shown as an attribute in the MIDlet suite's Java Application Descriptor (JAD) file.

Enabling a Push Registry Entry

To make use of the Push Registry, you must also have permission to access the Push Registry API, `javax.microedition.io.PushRegistry`. API permission, are handled in the API Permissions property page ("[API Permissions](#)").

Remove a Push Registry Entry

Select an entry and click Remove to delete it from the list.

Change Push Registry Display Order

The list order determines the order in which the MIDlets are displayed. Select an entry and select **Move Up** or **Move Down** to change its position.

API Permissions

These properties set permission attributes for protected APIs called by the MIDlet suite. To view this property page, right-click on a project and click **Properties**. Select the Application Descriptor category, and select the API Permissions tab.

Adding Permission Requests

1. Click the **Add**.

The Add Permission for API dialog opens.
2. Select an API package from the dropdown list or enter an API package name into the combo box and click **OK**.

3. (Optional) In the Requested Permissions table, check the Required box if you want installation to fail when that permission cannot be granted.

For more information, see *Security for MIDP Applications* in the MIDP 2.1 (JSR 118) specification, available at:

<http://jcp.org/aboutJava/communityprocess/mrel/jsr118/index.html>

Building a Project

When you build a project, the SDK compiles the source files and generates the packaged build output (a JAR file) for your project. You can build the main project and all of its required projects, or build any project individually.

In general you do not need to build the project or compile individual classes to run the project. By default, the SDK automatically compiles classes when you save them. You can use properties to modify the following build tasks:

- "Compiling"
- "Adding Libraries and Resources"
- "Obfuscating"
- "Creating JAR and JAD Files (Packaging)"
- "Signing"

Configuring Ant

To view this form, follow these steps:

1. Click the **Tools** menu and select **Options**.
2. Select Java and click the Ant tab.

Ant Home. The installation directory of the Ant executable the SDK uses. To change Ant versions, type the full path to a new Ant installation directory in this field or click Browse to find the location. You can only switch between versions 1.5.3 and higher of Ant. The Ant installation directory must contain a `lib` subdirectory which contains the `ant.jar` binary. If you enter a directory that does not match the expected structure, the SDK gives you an error. See the NetBeans help topic for more options.

Save All Modified Files Before Running Ant. If selected, saves all unsaved files in the SDK before running Ant. It is recommended to leave this property selected because modifications to files in the SDK are not recognized by Ant unless they are first saved to disk.

Reuse Output Tabs from Finished Processes. If selected, writes Ant output to a single Output window tab, deleting the output from the previous process. If not selected, opens a new tab for each Ant process.

Always Show Output. If selected, the SDK displays the Output window for all Ant processes. If not selected, raises the Output window tab only if the Ant output requires user input or contains a hyperlink. Output that contains hyperlinks usually denotes an error or warning.

Verbosity Level. Sets the amount of compilation output. Set the verbosity lower to suppress informational messages or higher to get more detailed information.

Classpath. Contains binaries and libraries that are added to Ant's classpath. Click **Add Directory** or **Add JAR/ZIP** to open the Classpath Editor.

Properties. Configures custom properties to pass to an Ant script each time you call Ant. Click Manage Properties to edit the properties in the property editor. This property is similar to the Ant command-line option, `-Dkey=value`. The following default properties are available:

`\${build.compiler.emacs}. Setting this property to true enables Emacs-compatible error messages.

Compiling

To view this property page, right-click a project and select **Properties**. In the Properties window Build category, select Compiling.

This page enables you to set the following options:

Generate Debugging Info. If checked, the compiler generates line numbers and source files information. This is the `-g` option in `javac`. If unchecked, no debugging information is generated (the `-g:none` option in `javac`).

Debug Block Level. The block level can be set to: `debug`, `info`, `warn`, `error`, and `fatal`.

Compile with Optimization. If checked, the compiled application is optimized for execution. This is the `-O` option in `javac`. Optimizing can slow down compilation, produce larger class files, and make the program difficult to debug.

Report Uses of Deprecated APIs. If checked, the compiler lists each use or override of a deprecated member or class. This is the `-deprecated` option in `javac`. If unchecked, the compiler shows only the names of source files that use or override deprecated members or classes.

Encoding. Overrides default encoding used by preprocessor and compiler. The default value is the default encoding used by your VM.

Adding Libraries and Resources

To view this property page, right-click on a project and select **Properties**. In the Properties window Build category, select Libraries and Resources to add a dependent project, libraries, and other supporting files to the current project.

Add Project. A JAR file produced by another project and the associated source files and Javadoc documentation. Adding this item to a classpath sets up a dependency between the current project and the selected JAR file.

Add Library. A Library is a collection of JAR files or folders with compiled classes, which can optionally have associated source files and Javadoc documentation.

Add Jar/Zip. A JAR file created by another project.

Add Folder. The root of a package or directory containing files.

When a library or resource is added, it is visible in the **Libraries & Resources** table, which reflects the order of the libraries and resources in the classpath. To change the order in the classpath, select the listing and click Move Up or Move Down. You can also remove libraries and resources from this page.

Each row in the table has a Package check box. If Package is checked, the library or resource is bundled and added to the project JAR file. If Package is not checked, the library or resource is copied to the `lib` subdirectory at build time.

Creating JAR and JAD Files (Packaging)

To view this property page, right-click on a project and select **Properties**. In the Properties window Build category, select Creating JAR.

You can set the following options:

JAD File Name. Name of the JAD file created by the project sources. The file name must have a .jad extension.

JAR File Name. Name of the JAR file created by the project sources. The file name must have a .jar extension.

Compress JAR. If checked, the JAR file is compressed.

Obfuscating

To view this property page, right-click on a project and select **Properties**. In the Properties window Build category, select Obfuscating.

Use the Obfuscation properties page to set the level of obfuscation for project files.

Move the Obfuscation slider to set the level. The Level Description window describes the impact each level has.

You can add more obfuscation parameters in the Additional Obfuscation Settings window.

Signing

To view this property page, right-click on a project and select **Properties**. In the Properties window Build category, select Signing. These properties enable you to enable signing and assign key pairs to a CLDC project. See ["Security Domains."](#)

Sign Distribution. Check this box to enable signing for the MIDlet suite. If it is unchecked, this page is disabled.

Keystore. A file that stores one or more key pairs as a keystore (.ks) file. The dropdown menu lists all available keystores. Click the Unlock button to unlock a keystore with the keystore password.

Alias. A name assigned to a key pair within a keystore. The dropdown menu lists the aliases available for the selected keystore. Click the Unlock button to unlock a key pair for use.

The Certificate Details window provides information about the certificate assigned to the key pair.

Click **Open Keystores Manager** to manage keystores and key pairs. See ["Managing Keystores and Key Pairs"](#) and ["Exporting a Key."](#)

Signing CDC Projects

To sign a CDC project use the JDK jarsigner command from the command line. For example: `jarsigner.exe -keystore keystore.ks -storepass keystorepwd MyCdcApp.jar dummyCA`

Exporting a Key

Follow these steps to export a key into an emulator:

- Click the **Tools** menu and select **Keystores**. This opens the Keystores Manager.

You can use the Keystores Manager to add a keystore to the Keystores list. Click **Add Keystore**. After you create the keystore, click New to create a key pair.

- In the Keys area, select a key, and click Export. This opens the dialog Export Key into Oracle Java ME SDK/Platform/Emulator.
- Select the target emulator from the Emulator list.
- Select the Security Domain.
- Click **Export** to export your key pair to the selected emulator.

Your key is added to the bottom of the list in Keys Registered in the Emulator.

The Export window has the following components:

Keystore File. Displays the name of the keystore file to which the key pair belongs. This field cannot be edited.

Key Pair Alias. The name given to the key pair within the keystore. This field cannot be edited.

Certificate Details. Displays the details of the certificate of the key to be exported.

Emulator. The drop-down menu lists all the device emulators available. See "[Security Domains](#)."

Security Domain. Enables you to select a security domain for the key pair. The menu lists all domains supported by the selected emulator platform.

Keys Registered in the Emulator. Lists all keys that have been registered in the selected platform. Click to select the key you want to export.

Delete Key. Deletes a selected key from the Keys Registered in the Emulator window.


Export. Exports the selected key to the selected emulator. The export button is enabled if it is possible to export the key. If a specific key is installed it cannot be installed again.

Running Settings

To view this property page, right-click a project and select Properties. In the Properties window, select Running. The options shown depend on the platform. See "[MIDP Project Run Options](#)" and "[CDC Project Run Options](#)."

MIDP Project Run Options

To set emulator command line options for a MIDP project, type in the command line switches. See "[Emulator Command Line Options](#)."

Figure 6–1 Emulator Command Line Switches

For CLDC projects, the Regular execution button is enabled by default. The setting for "Specify the Security Domain" applies when the project is run on an emulator. It does not apply for OTA provisioning or an external emulator platform.

If you do not check Specify the Security Domain the project runs with the default that was assigned when the project was created. If you check the box, you can select a domain from the dropdown list. See ["Security Domains"](#) and ["Specify the Security Domain for a Project."](#)

CDC Project Run Options

For CDC projects you must enter the name of the entry point Java file in the Main Class field. The Main Class Browse button only shows executable classes in the project's source folders. For a CDC project you see all classes with a static main method, or classes extending the Applet or Xlet classes.

Arguments are passed only to the main class, not to individual files. If an Xlet is executed, all arguments are passed to all the Xlets you specify.

For VM options, see ["CDC Options."](#)

Working With Devices

The Oracle Java ME SDK provides default device skins. A skin is a thin layer on top of the emulator implementation that defines the appearance, screen characteristics, and input controls. This chapter discusses the default emulators provided by Oracle Java ME SDK and describes how you can create and modify a custom device. To make your own device, see ["Using the Custom Device Editor."](#)

The Oracle Java ME SDK emulator simulates a CLDC, CDC, IMP-NG, or Qualcomm device on your desktop computer. The CLDC, CDC, and IMP-NG emulators do not represent a specific device, but provide correct implementations of the supported APIs for these platforms.

The Qualcomm_IoE_Device emulator provides an emulation of the Qualcomm Orion IoE embedded device. For more information on the Qualcomm Orion IoE device, see the Oracle Java ME Embedded *Getting Started Guide for the Reference Platform (Qualcomm Orion IoE)*.

The Device Manager on Windows

The Oracle Java ME SDK uses the Device Manager to detect devices and displays the available devices in the Device Selector window (**Tools > Java ME > Device Selector**). The Device Manager is a service used to manage both emulators and external devices.


The Device Manager runs in your Windows system tray. Once you have installed the Oracle Java ME SDK software, it starts automatically when you start Windows. In the task manager, the process is labeled `device-manager.exe`.

Figure 7-1 The Device Manager Icon




You can right-click the icon and select **Exit** to stop the service. To restart the Device Manager, double-click `device-manager.exe` in your `installdir\bin` directory. You can also start it from the command line as described in ["Run the Device Manager."](#)

In the Windows system tray, click the icon or right-click the icon and select **Manage Device Addresses** from the menu to open the Device Address Manager, as shown in [Figure 7-2](#).


Figure 7-2 The Device Manager Menu

Enter an IP address and select **Add** to add a device. Select an address and click **Remove** if you have an address you no longer want to detect. The device is no longer displayed in the Device Selector.

If an embedded device is attached, the user can select a COM port for the hardware connection in the Select COM Port field. If Disable is selected, Oracle Java ME SDK stops detecting external devices via COM port, as shown in [Figure 7-3](#).

Figure 7-3 The Device Address Manager

Right-click the icon in the system tray and select Registered Devices to see a list of registered devices and their configuration information such as, screen dimensions, screen depth, security domains, supported APIs, and more, as shown in [Figure 7-4](#).

Figure 7–4 The Registered Devices Screen


Adding an External Device

The device selector can detect a device that has a compatible runtime. Typically this device has network capabilities and is connected to the computer running Oracle Java ME SDK.

1. To detect a physical device, click CTRL-D, or click the device icon at the top of the Device Selector window.
2. Type an IP address and click **Next**. Click **Finish**.

You can also enter an IP address in the Device Manager, as described in ["The Device Manager on Windows."](#)

3. The physical device is listed in the appropriate platform tree. By default, the device has "ExternalDevice" appended to the name.
For example, if an IMP-NG device is detected it is placed in the IMP-NG node and given the name IMPNGExternalDevice1.
4. If your device is supported by a serial connection, you can define a port for the connection in the Device Address Manager. To define a COM port, click the Select COM Port field and select a port, as shown in [Figure 7–5](#).

Figure 7-5 Adding a COM Port

The Oracle Java ME SDK provides support for several embedded external devices through the Oracle Java ME Embedded runtime, including:

- Keil MCBSTM32F200
- Raspberry Pi
- Qualcomm Orion IoE

For additional information on how to install, configure, and work with a supported external device, see the Oracle Java ME Embedded documentation at:

<http://docs.oracle.com/javame/embedded/embedded.html>

Starting and Running Emulators

The Oracle Java ME SDK runs applications on an emulator or an external device. Before you can run an application from the SDK, the Device Manager, must be running. When the Oracle Java ME SDK runs, the Device Manager automatically launches and starts detecting devices. The default emulators shipped with the SDK are automatically found and displayed in the NetBeans Device Selector window (**Tools > Java ME > Device Selector**).

Starting an Emulator

Typically an emulator is launched when a Oracle Java ME SDK project is run from the NetBeans IDE or the command line. The default emulator is determined by the Java ME platform selected for the project, as described in "[Managing Java Platforms](#)."


You can open an emulator without running an application from the IDE. From the Windows Start menu, click **Programs -> All Programs** and select **Java(TM) ME Platform SDK 3.4**. On the pull-right menu, select the desired emulator. You can also click the emulator shortcuts installed on your Windows desktop.

To run an application from the emulator, click the **Application** menu and select **Run MIDlet Suite** (or **Run IMlet Suite**). Provide the path to the application and any other information, and click OK.

The IMP-NG Emulator

IMP-NG is a Java ME profile commonly used on small embedded devices. [Figure 7–6](#) shows the IMP-NG emulator provided in Oracle Java ME SDK.

Figure 7–6 The IMP-NG Emulator



Device Name. Shown in the upper window frame. See [Table 8–1](#) for a list default emulator names.

Menus. See "[Emulator Menu Settings](#)."

Toolbar. For the IMP-NG Emulator, the Toolbar provides shortcuts for the following operations:

- Run IMlet Suite
- Install IMlet Suite
- External Events Generator

- Emulator window always on top

Note: When the Device Manager detects an external IMP-NG device, only the Application, View, and Help menus and the Run IMlet Suite, Install IMlet Suite, and Emulator window always on top icons in the Toolbar are available in the device display.

Device ID. Numerical identifier that is unique for each device.

Display Panel and Tabs. The display panel displays fields and information dependent on the selected tab:

- **AMS.** The AMS (Application Management System) tab displays the name of the IMlet suite, the IMlet, and the status of the IMlet suite. You can select a suite and perform one of the following operations by clicking the corresponding button to the right of the display:
 - **Install** - Specify the location of the IMlet suite path or URL and the security domain and click OK to load the IMlet suite.
 - **Update** - Check for any updates to the application and performs the update.
 - **Info** - Open a dialog box displaying the application name, vendor name, version, description of the application, class name, and the URL.
 - **Run** - Run the selected application. This button is only visible for an installed application that is not running.
 - **Suspend (Resume)** - Pause the running IMlet. This button toggles to Resume when execution is paused.
 - **Stop** - Stop execution of the application. This button is only visible for a running application.
 - **Remove** - Remove the application.
- **GPIO Pins.** The General Purpose Input Output (GPIO) Pins tab displays which pins are selected to output and their high or low values.
- **GPIO Ports.** The GPIO Ports tab displays a list of ports, which ports are selected to output, and their maximum and current values.
- **I2C.** The Inter-Integrated Circuit (I2C) tab displays information for the selected slave device and data sent to a master device and data received from a master device.
- **SPI.** In the default SPI implementation, buffered written data can be read from the Slave named SPI. If you have created a custom implementation with the Custom Device Editor, the Slave drop down list might have additional slaves.
- **MMIO.** The memory-mapped I/O tab displays information for the current device.
- **ADC.** The Analog-to-Digital Converter tab displays the current channel, converter number, sampling intervals, minimum and maximum values, and other information.
- **DAC.** The Digital-to-Analog Converter tab displays the current channel information, converter characteristics, and a graphic display of signal characteristics with the x-axis showing the digital input and the y-axis showing the analog output.

- **Pulse Counters.** The Pulse Counters tab displays the ID, counter name, counter number, counter type, and the pins to which the counters are bound.

Emulator Status Bar. Information about the current system state is shown in the status bar at the bottom of the emulator window. Also shown is the memory indicator showing used and total memory.

The External Events Generator

The following menu options each have a tab on the External Events Generator. The use of the External Events Generator is addressed in the discussion for each JSR:

- **ADC.** The Analog-to-Digital Conversion tab is only visible for the IMP-NG emulator.
- **Access Points.** This tab displays connection information for the selected access point.
- **GPIO.** This General Purpose Input Output (GPIO) option.

By default, this tab displays ports and pins for a specific device described in ["Running the GPIODemo."](#) You can create a custom device to represent a different device. See ["General Purpose Input Output \(GPIO\)."](#)

See the Device Access API (*installldir\docs\api\deviceaccess*) for a description of the GPIO interface.

- **Location.** ["Setting the Emulator's Location at Runtime."](#)
- **MMIO.** The memory-mapped I/O (MMIO) option is visible only for the IMP-NG emulator. From the Device drop down list, select one of the default devices:
 - **TEST_DEVICE.** A Little Endian device that contains all block types: byte, short, int, long, and block. Writes to this device also affect BIG_ENDIAN_DEVICE which shares the address space.
 - **WDOGLOG.** A Little Endian device that supports only the block type.
 - **RTC.** STM32F200 RTC device. A Little Endian device that supports only the int type.
 - **BIG_ENDIAN_DEVICE.** A Big Endian device that shares the address space with the TEST_DEVICE, therefore it contains the same memory blocks. Writes to this device also affect TEST_DEVICE which shares the address space.

If you are using a custom device created with the Custom Device Editor (see ["Using the Custom Device Editor"](#)). The device list might include additional devices.

See the Device Access API (*installldir\docs\api\deviceaccess*) and the Embedded Support API (*installldir\docs\api\embedded-support-api*) for descriptions of the MMIO interface.

- **Mobile.** The unique International Mobile Subscriber Identity (IMSI) and the International Mobile Station Equipment identity (IMEI) identifiers of the device.
- **Pulse Counter.** This tab displays the current pulse counters on the device. The default configurations are:
 - COUNTER_PA0
 - COUNTER_PB3
 - COUNTER_PB10

- COUNTER_PA3

You can configure the pulse counters you want and send a signal to the configured pulse counter by clicking **Send Pulse**.

IMP-NG Device Options

For in-depth descriptions of the IMP-NG interfaces or devices, see the following resources:

- *Device Access API* (*installdir\docs\api\deviceaccess*)
- *Embedded Support API* (*installdir\docs\api\embedded-support-api*)
- For more information about default devices and their properties, you can use the Properties View from the Device Selector. For more information, see "[Viewing Device Properties](#)."

The Qualcomm IoE Emulator

The Qualcomm_IoE_Device emulator is based on IMP-NG, but for a specific embedded platform, the Qualcomm Orion IoE device. Many of the menus and settings are the same as in the IMP-NG emulator.

For more information on Qualcomm_IoE_Device emulator menus and settings that are not mentioned in this section, see "[The IMP-NG Emulator](#)."

The Qualcomm_IoE_Device emulator is launched from the Windows command prompt:

1. Change to the bin directory of the Oracle Java ME SDK distribution:

```
C:\>cd Java_ME_platform_SDK_3.4\bin
```


2. Enter the following command, as shown here:

```
emulator.exe -Xdevice:Qualcomm_IoE_Device -Xdescriptor:location_of_jad_file
```

For example:

```
emulator.exe -Xdevice:Qualcomm_IoE_Device -Xdescriptor:C:\Java_ME_
platform_SDK_3.4\apps\sample\sample_imlet.jad
```

This launches the Qualcomm_IoE_Device emulator, as shown in [Figure 7-7](#).


Figure 7-7 The Qualcomm_IoE_Device Emulator

The External Events Generator

The tabs on the External Events Generator for the Qualcomm_IoE_Device emulator largely match those of the IMP-NG emulator. Those that differ are shown below.

The Serial Peripheral Interface (SPI) Tab

The Qualcomm_IoE_Device emulator External Events Generator SPI tab provides a sample accelerometer sensor, G-Sensor, as shown in [Figure 7-8](#).

Figure 7–8 The External Events Generator SPI Tab

The G-Sensor sample allows an IMlet to read accelerometer values from the emulator through the Serial Peripheral Interface. Move the slider of the X, Y, and Z acceleration scale to change the x, y, and z values transmitted over SPI. The minimum and maximum values for the sliders in the G-Sensor are defined by the Java ME application.

The G-Sensor sample duplicates in emulation the functionality of the digital, triaxial acceleration sensor on the Qualcomm Orion IoE embedded device. The acceleration sensor is used to sense tilt, motion, and shock vibration in embedded devices, such as medical instruments, computer peripherals, and monitoring devices.

The G-Sensor Fields

The G-Sensor has the following fields:


- **Range.** Allows you to specify a range to be sensed.
- **Bandwidth.** Allows you to specify a bandwidth to be sensed.
- **Accelerator-X.** Allows you to select a value within a specified range by moving the slider position.
- **Accelerator-Y.** Allows you to select a value within a specified range by moving the slider position.
- **Accelerator-Z.** Allows you to select a value within a specified range by moving the slider position.

For more information on working with the Qualcomm Orion IoE embedded device, see the Oracle Java ME Embedded *Getting Started Guide for the Reference Platform (Qualcomm Orion IoE)*.

The Inter-Integrated Circuit (I2C) Tab

The Inter-Integrated Circuit (I2C) tab displays information for the selected slave device, and data sent to and received from a master device. The Qualcomm_IoE_Device emulator External Events Generator I2C tab provides three sample sensors, as shown in [Figure 7–9](#).

Figure 7–9 The External Events Generator I2C Tab with Available Sensors



The three sample sensors in the I2C tab are:

- **G-Sensor.** Operates in the same way as described in the External Events Generator SPI tab. However, the sample IMLet reads the accelerometer values through the I2C interface. For more information, see "[The Serial Peripheral Interface \(SPI\) Tab.](#)"
- **Light Sensor.** Allows the user to test three kinds of light sensing: ambient light, proximity, and Infrared (IR). A lux value can be specified, and the values changed within the lux value range by moving the Light slider.
- **Temperature Sensor.** High and Low temperature values can be set, and temperature values read when the slider is moved.

The Light Sensor Fields

The Light Sensor has the following fields:

- **Type.** Three types of light sensing are possible:
 - Ambient Light. Allows changes in light brightness to be registered by the emulated sensor.
 - Proximity. Allows changes in light proximity (distance) to be registered by the emulated sensor.
 - Infrared (IR). Allows changes in infrared light to be registered by the emulated sensor.
- **Range.** Four values of illuminance (luminous flux) are possible:
 - 1. (0.015 - 100 lux)
 - 2. (0.06 - 4000 lux)
 - 3. (0.24 - 16000 lux)
 - 4. (0.96 - 64000 lux)
- **Resolution.** Allows, 4, 8, 12, or 16 bits.
- **Low Limit (lux).** Defined by the value set in the Range field.
- **High Limit (lux).** Defined by the value set in the Range field.
- **Interrupt Flag Set.** If the user changes the sensor value and the new value is out of the High-Low Limits interval, the Interrupt Flag is set to Yes and the Java ME application reads the value. If the sensor values stay within the defined range, the Interrupt Flag is not set and the value is No. If the Interrupt Flag is set to Yes and the values returned within the defined range, the Interrupt Flag is reset to No.
- **Light (lux).** Allows the user to define the lux value for the application by moving the slider. The high and low lux limits are defined by the value set in the Range field.

The Temperature Sensor Fields

The Temperature Sensor has the following fields:

- **Low Temperature Limit (Celsius).** Defines a low temperature setting, beyond which a Limit Flag is tripped. Has a corresponding Limit Tripped field.
- **High Temperature Limit (Celsius).** Defines a high temperature setting, beyond which a Limit Flag is tripped. Has a corresponding Limit Tripped field.
- **Limit Tripped.** Applies to both High and Low Temperature fields. If the user moves the slider and the new value is outside the High or Low Limits, the Limit Tripped flag is set to Yes and the Java ME application reads the value in Status Register 1. When the Limit Tripped value is read in Status Register 1, the Limit Tripped flag is reset to No. If the slider values stay within the defined range, no Limit Tripped flag is set and the value is No.
- **Temperature (Celsius).** Allows the user to define the temperature value for the application by moving the slider. The high and low temperature limits are defined by the value set in the Low Temperature and High Temperature fields.

The Temperature Sensor can operate in Default or Extended mode.

- In Default mode, the user can change the temperature from 0 to 127 degrees Celsius.


- In Extended mode, the user can change the temperature from -64 to 191 degrees Celsius.

To set the Default or Extended mode, use `setDefaultMode()` and `setExtendedMode()` in the Java ME application.

The CLDC Mobile Emulator

The Oracle Java ME SDK provides a Mobile emulator based on CLDC, as shown in [Figure 7-10](#).

Figure 7-10 *Emulator Features*



CLDC Application Management System

The CLDC AMS home screen features three utilities:


- **Install Application.** This utility opens a form in which you can specify a URL (or a file path) for a JAD file to install.
- **Manage Certificate Authorities.** This feature displays the certificates authorities for the device. In this interface the white box indicates the certificate is checked (active). You can uncheck certificates that are not needed.
- **Output Console.** The output console displays system output statements from a running application. The application must write to the Java standard output console using, for example:

```
System.out.println("text");
```

Start the emulator's Output Console, then start your application. Use F7, Switch running MIDlet, to switch between the application and the Output Console.

Note that the emulator's Output Console is an application that consumes resources. If you get the message "No more concurrent applications allowed," you must close some applications before continuing.

Figure 7-11 The Output Console Window



See ["The CLDC Mobile Emulator"](#) and ["Emulator Menu Settings."](#)

You can also access system output information from the emulator by clicking the **View** menu and selecting **Output Console...**, which opens an Output Console dialog box. Select a filter from the drop down list to display specific system output. Click **Save** to save the output as a .log file.

Mobile Emulator Menus

Device Name. Shown in the upper window frame. See [Table 8-1](#) for a list of default emulator names.

Transmission Indicator. On the upper left of the emulator image, this blue light turns on when a transmission is occurring. Typically you see it when an application is installed over-the-air, or when a message is being sent or received. For example, when you receive a message from the WMA console.

Menus. See "[Emulator Menu Settings](#)."

Toolbar. For the CLDC emulator, the Toolbar provides shortcuts for the following operations:

- Run MIDlet Suite
- Install MIDlet Suite
- Resume
- Suspend
- Rotate Clockwise
- Rotate Counterclockwise
- External Events Generator
- Emulator window always on top

Device ID. Numerical identifier that is unique for each device.

Exit Button. On the upper right of the emulator image, is the termination button. Pushing this button the same effect as clicking **Application** and selecting **Exit**.

Emulator Status Bar. Information about the current system state is shown in the status bar at the bottom of the emulator window.

Running Projects Simultaneously on a Single Device

CLDC-based devices are capable of running multiple virtual machines. To test this feature, follow these steps:

1. Display the Output window. Select **Window > Output > Output**.

The Output window does not need to be open to run this procedure. You can open the Output window at any time to display all output from the beginning of the emulator session.

2. Open the sample projects Games and AudioDemo.

3. In the device selector, select a CLDC device and run Games. When the emulator launches, run AudioDemo on the same device.

As each MIDlet loads, the AMS automatically installs it.

4. In AudioDemo, launch the Audio Player, and play the JavaOne theme.

Select AudioPlayer, then from the soft menu, select 1, Launch. Select JavaOne Theme and press the Play soft button.

5. In the emulator, click the **Application** menu and select **AMS Home**, or press F4.

Select **Games**. From the soft menu, select 1, Open. The music continues to play while you are able to simultaneously launch and play games.

6. Click the **Application** menu and select **AMS Home**, or press F4. Highlight AudioSamples, and from the soft menu, select 2, Bring to foreground. Press the Pause soft key. The music stops playing.

7. Click the **Application** menu and select **AMS Home**, or press F4. Highlight AudioSamples and from the soft menu, select 1, Open. Select Bouncing Ball from the list and press the Launch soft button. Select MIDI background and press the Play soft button.
8. Click the **Application** menu and select **AMS Home**, or press F4. Then click the **Application** menu and select **Switch Running MIDlet**. Select Audio Player and press the Switch to soft button. You can press the Play soft button to resume the Audio Player.

Emulator Menu Settings

The Menus available on the three Oracle Java ME SDK emulators are very similar, with differing suboptions. The following tables describe the operations of each menu in more detail.

- The IMP-NG emulator has Application, Device, Tools, View, and Help menus.
- The Qualcomm_IoE_Device emulator has Application, Device, Tools, View, and Help menus.
- The CLDC (Mobile) emulator has Application, Device, Edit, Tools, View, and Help menus.
- The CDC emulator has Application, View, and Help menus.

Note: The View and Help menus are the same on CDC and CLDC platforms. For CDC, the Device menu is not populated, and Application menu contains only the Exit option

The Application Menu

The Application menu is fully populated for the CLDC platform. [Table 7–1](#) describes the Application options:

Table 7–1 *Emulator Application Menu*

Option	Accelerator	Description
Install MIDlet Suite		Permanently add a MIDlet suite to the emulator. Enter the path or URL of the MIDlet suite to install on the emulator. Select the desired level of the permissions in the Security Domain field.
Install IMlet Suite		Permanently add a IMlet suite to the emulator. (IMP-NG emulator) Enter the path or URL of the IMlet suite to install on the emulator. Select the desired level of the permissions in the Security Domain field.
Run MIDlet Suite		Emulator interface for launching MIDlets.
Run IMlet suite		Emulator interface for launching IMlets. (IMP-NG platform)
AMS Home	F4	Exit the current application and return to the Application Management Software home. (CLDC emulator)
Stop	F10	Stops the currently running MIDlet. (CLDC emulator)

Table 7–1 (Cont.) Emulator Application Menu

Option	Accelerator	Description
Change Locale		This option only works with localized MIDlets. (CLDC emulator) Enter a locale identifier. The format is similar to Java SE 6, as follows: 2-letter-lang-code <i>separator</i> 2-letter-country-code For example, en-US, cs-CZ, zh-CN, ja-JP. The separator can be a dash or an underscore.
Resume	F6	Resume a suspended application. (CLDC emulator)
Suspend	F5	Pause a running application. (CLDC emulator) Do not use this option if you are running the memory monitor.
Switch Running MIDlet	F7	When you have multiple MIDlets running, toggle between them. You see a list of running MIDlets and you can chose the one you want to switch to. See "Running Projects Simultaneously on a Single Device" (CLDC emulator).
Exit	Exit button on emulator upper right	Close the emulator process and stop the build process (or processes).

The Device Menu

This menu is available on CLDC and IMP-NG platforms.

Messages

Click the **Device** menu and select **Messages** to see what is written in the message area. This is the emulator's Inbox. The Inbox displays WMA messages that are addressed to the device, not an application on the device. Messages are sent to this interface in the following cases:

- An MMS message is sent without an AppID in the address
- An SMS message is sent without a port in the address (or the port number is 0)
- An SMS text message is sent with a port in the address, but there is not a Java ME application listening on the specified port

To test sending messages to the inbox use the WMA Console in NetBeans, or from the command line, use `wma-tool.exe` to send SMS messages. Note, `wma-tool.exe` requires an AppID for MMS, so `wma-tool` cannot be used to send an MMS.

Orientation

This option is only visible for the CLDC emulator.

Use this feature to test your application's ability to display in portrait and landscape formats. The default is 0 degrees. Change the orientation to 90, 180, or 270 degrees. You can also rotate 90 degrees clockwise (F8) or counterclockwise (F9) from the current position.

The Edit Menu

[Table 7–2](#) describes the Edit menu, which provides basic editing operations for the CLDC platform.

Table 7–2 Emulator Edit Menu

Option	Accelerator	Description
Copy	CTRL-C	Copy selected material to the paste buffer.
Cut	CTRL-X	Move selected material to the paste buffer.
Paste	CTRL-V	Insert the contents of the paste buffer.

The Tools Menu

[Table 7–3](#) describes the utilities accessible from the Tools menu.

Table 7–3 Emulator Tools Menu

Option	Description
Manage Landmarks	Opens the Landmark Store utility. In this interface, you can view and edit a landmark store installed as part of an application. You can also create a new landmark store, define landmarks, define landmark categories, and assign landmarks to categories.
Manage File System	Opens the File System manager and displays the mounted file system root directories. You can mount or unmount a file system directory, copy a mounted file system directory, remount or remove directories. For a description of managing a file system, click the Tools menu and select Manage File System. Click Help in the dialog box.
External Events Generator	Opens the External Events Generator. The External Events Generator provides a way to interact with an application by injecting events. The interaction may be through a user interface, or through a script file. For a description of the External Events Generator, see "The External Events Generator."
Take Screenshot	Takes a screenshot of the emulator display screen and saves it to the clipboard. (CLDC emulator)

The View Menu

[Table 7–4](#) describes the View menu, which is available for the CLDC, CDC, and IMP-NG platforms.

Table 7–4 Emulator View Menu

Option	Description
Always On Top	Keeps the emulator in the foreground. This option is especially useful when you are running multiple emulator instances and you want to see them all and send messages between devices.

Table 7–4 (Cont.) Emulator View Menu

Option	Description
Output Console	Displays system output statements from a running application in the Output Console window. You can filter the output statements for IMP-NG emulators by selecting All, Standard, or Error from the Show dropdown list. Error messages are highlighted. Filtering of output statements and highlighting of error messages are not available for CLDC emulators or external devices. You can save system output information to a .log file by clicking Save in the window.
Device Log	Displays emulator log messages in the Device Log window. The following filters are available from the Level dropdown list: ■ Trace - Tracing information, such as garbage collection, exceptions, and method calls. ■ Debug - General debugging information. ■ Info - Information messages. ■ Warn - Alerts that issues were encountered during runtime. Warnings are highlighted. ■ Error - Errors encountered during runtime but do not prevent the application from running. Error messages are highlighted. ■ Fatal - Non-recoverable errors that can potentially prevent the application from running and might cause the application to quit. You can save system output information to a .log file by clicking Save in the window.


The Help Menu

The Help menu displays an abbreviated helpset specifically for the emulator window.

Using the Device Selector

The Device Selector lists the devices currently available in NetBeans, grouped by platform, as shown in [Figure 7–12](#).

If the Device Selector is not visible, click on the Device Selector tab, or select **Tools > Java ME > Device Selector**.

Figure 7–12 The Device Selector

The list in the Device Selector matches the list displayed in the Registered Devices window.

Viewing Device Properties

If no Java ME platform is registered in NetBeans, the Device Selector displays a node labeled No Device Found. If you see this message at startup, it typically means device discovery is incomplete and you must wait a few seconds.


Each sub node represents a device. Two instances are provided for some CLDC devices, for example, JavaMEPhone1 and JavaMEPhone2. Instances of the same device have the same capabilities but unique names and phone numbers, making it easy for you to test communication between devices of the same type. To make your own device, see ["Using the Custom Device Editor."](#)

For Device names, see ["Oracle Java ME SDK Directories."](#) The properties for each device are stored in XML files in your user work directory. See [Table 8–1](#).

Platform Properties

To view platform properties from the device selector, click on the platform node (for example, CLDC or IMP-NG). The Properties window is, by default, docked in the upper right portion of the user interface. If the Properties window is not visible, click the **Windows** menu and select **Properties**.

To view the platform properties in a separate window, right-click the platform node and select Properties. This displays a Properties window for the selected device, as shown in [Figure 7–13](#).

Figure 7–13 Separate Device Properties Window

The information in the docked properties window and the separate window is the same.

Device Information

In the Device Selector window, double-click a device node. The Device Information tab opens in the central Main window. It displays a picture of the device and displays details, supported hardware capabilities, keyboard support, supported media formats, and the supported runtimes.

Device Properties

In the Device Selector window, click a device node (such as JavaMEPhone1) to display the device properties. The Properties window is, by default, docked in the upper right portion of the user interface. If the Properties window is not visible, click the **Windows** menu and select **Properties**.

Setting Device Properties

In the Device Selector window, right-click a device and select **Properties**. Any properties shown in gray font cannot be changed. You can adjust the device properties shown in black. Only CLDC and IMP-NG options can be adjusted. The CDC options cannot be changed.

General Device Properties

This section lists general properties that can be changed.

Phone Number. You can set the phone number to any appropriate sequence, considering country codes, area codes, and so forth. If you reset this value, the setting applies to future instances. The number is a base value for the selected device.

Heapsize. The heap is the memory allocated on a device to store your applications's objects. The Heapsize property is the maximum heap size for the emulator. You can select a new maximum size from the drop down menu.

Security Domain. Select a security setting from the drop down menu. See "[Specify the Security Domain for an Emulator.](#)" Applies to CLDC platforms.

JAM storage size in KB. The amount of space available for applications installed over the air.

Locale. Type in the locale as defined in the MIDP 2.1 specification at:

<http://download.oracle.com/otndocs/jcp/midp-2.1-mrel-oth-JSpec>

Remove MIDlet Suite in execution mode. If this option is enabled, record stores and other resources created by the MIDlet are removed when you exit the MIDlet (assuming the MIDlet was started in execution mode).

Monitor

If enabled (checked), the Check boxes for Trace GC (garbage collection), Trace Class Loading, Trace Exceptions, and Trace Method Calls activate tracing for the device the next time the emulator is launched. The trace output is displayed at runtime in the user interface Output window. Trace Method Calls returns many messages, and emulator performance can be affected. See [Chapter 11, "Monitoring Memory."](#)

IMP-NG Device Properties

When you create a new IMP-NG device using the Custom Device Editor (**Run > Custom Device Editor**) you can use the default implementation or create your own custom implementation for the interfaces discussed in this section.

See the following resources for in-depth descriptions of the IMP-NG interfaces or devices:

- *Device Access API* (*installdir\docs\api\deviceaccess*)
- *Embedded Support API* (*installdir\docs\api\embedded-support-api*)
- For more information about default devices and their properties, you can use the Properites View from the Device Selector. For more information, see "[Viewing Device Properties.](#)"

General Purpose Input Output (GPIO) A GPIO port is a platform-defined grouping of GPIO pins that may be configured for output or input. Output ports are both writable and readable while input ports are only readable. Note that GPIO pins that are part of a GPIO port cannot be retrieved nor controlled individually as GPIO Pin instances.

Click **Add Port** to add entries to the Ports table. Each item in a Ports table row is editable. Check Output to set the port direction to output.

A GPIO pin may be configured for output or input. Output pins are both writable and readable while input pins are only readable. Note, an input listener can only be assigned to a pin set for input.

Click **Add Pin** to add a row to the Pins table. The ID and name are editable. Click **Output** to make a pin both readable and writable. Click in the Initial Value column to toggle the Initial Value from Low to High.

Inter-Integrated Circuit (I2C) and Serial Peripheral Interface (SPI) The process for configuring I2C and SPI interfaces is very similar.

On an I2C bus, data is transferred between the I2C master device and an I2C slave device through single or combined messages. On an SPI bus, data is transferred between the SPI master device and an SPI slave device in full duplex. That is, data is transmitted by the SPI master to the SPI slave at the same time data is received from the SPI slave by the SPI master. See the *Embedded Support API* for more details.

- Select Sample Echo to select the default bus implementation. This default implementation simply reads buffered written data from the slave.
- Select Custom to specify your own bus implementation.

1. Supply your bus implementation JAR file and the name of the Java class that implements the bus.

For I2C, the bus is:

```
com.oracle.jme.toolkit.deviceaccess.i2c.I2CSlaveBus
```

For SPI, the bus is:

```
com.oracle.jme.toolkit.deviceaccess.spi.SPISlaveBus
```

2. To add Slaves, click **Add** and specify an ID and Name. For SPI, specify the Word Length as well.

Note: On an SPI bus, data is transferred between the SPI master device and an SPI slave device in full duplex. So every `com.oracle.deviceaccess.spibus.SPIDevice.read(...)` method also writes an array of zeros to the slave device. The length of this array equals a length of read data. In the default implementation this array of zeros is appended to the loopback's buffer.

Memory-Mapped I/O (MMIO) The default devices are described in "[The External Events Generator](#)."

If you want to provide your own MMIO emulation, you must specify a custom handler.

Supply your implementation JAR file and the name of the Java class that implements `com.oracle.jme.toolkit.deviceaccess.mmio.MMIOHandler`. For comparison, the default JAR file is:

```
install\dir\toolkit-lib\devices\IMPNGDevice\code\emulator_deviceaccess_
mmio-sample-handler.jar
```

To add devices to the custom MMIO implementation, use the Devices and Device Memory tables as follows:

1. Click **Add Device** to add a row to the Devices table.
 - A default ID is assigned but you can double-click in the ID column to edit the value.
 - A default Name is supplied, but it can also be edited.

- In the Byte Ordering column, make a selection from the drop down list.
2. Click a row in the Device table to select a Device.
3. Click **Add Memory**.
 - In the Type column, make a selection from the drop down list. Double-click to edit the Address column entries.

If the type is Block, you can double-click to edit the Size column entries as well as the Address column entries.
4. Click **OK**.

Location Provider #1 and #2

These properties determine the selection of a location provider. Two providers are offered so that your application can test matching the location provider criteria.

If you select a property a short explanation is shown in the description area just below the Properties table. For more information on these values, see the Location API at:

<http://jcp.org/en/jsr/detail?id=179>.

SATSA

For more information on working with Security and Trust Services (SATSA), see [Chapter 20, "JSR 177: Smart Card Security \(SATSA\)."](#)

Bluetooth and OBEX

For more information on working with Bluetooth and Object Exchange (OBEX), see [Chapter 17, "JSR 82: Bluetooth and OBEX Support."](#)


Running a Project from the Device Selector

The SDK determines which open projects are suitable for a device. Right-click the device and select a project from the context menu.

You can also launch the emulator to run a project from the command line, as explained in ["Emulator Command Line Options."](#)+

Using the Custom Device Editor

With the Custom Device Editor you can create your own devices. The appearance of the custom devices is generic, but the functionality can be tailored to your own specifications. The Custom Device Editor is shown in [Figure 7-14](#).

Figure 7–14 The Custom Device Editor

Creating a Custom Device

Follow these steps to create a custom device.

1. Select **Tools > Java ME > Custom Device Editor**.

The custom device tree displays Java ME platforms and custom devices, if any.

Alternatively, you can launch the Custom Device Editor from the your installation's bin directory. For example:

```
C:\Java_ME_platform_SDK_3.4\bin\device-editor.exe
```

The custom device tree displays Java ME platforms and custom devices, if any.

2. Select a platform and click the **New...** button.
3. Change the default configuration to match your specifications, and click **OK**.

Your device is added to the custom device tree and eventually appears in the Device Selector. You can run projects from the IDE or from the command line from the custom device.

The custom device tree affects what appears in the Device Selector. For example, if you do not want a custom device to appear in the device selector, you must remove it from the custom device tree.

The device definition is saved in `install_dir\toolkit-lib\devices`.

Managing Custom Devices

Custom devices should always be managed using the Custom Device Editor. Using the tool ensures that your device can be detected and integrated with the Oracle Java ME SDK.

- **New.** Select a platform and click **New** to add a new device.
- **Edit.** Select a device to change, and click **Edit**.
- **Clone.** Select a device to copy, and click **Clone**. To prevent confusion, be sure to provide a unique name.

- **Remove.** Select a device to delete and click **Remove**. This action completely deletes the device.
- **Import.** Select a node in the custom device tree and click Import. Select a .zip file created with the Export command.
- **Export.** Select a device to save, and click **Export**.

When a custom device is created it is saved in *installdir\toolkit-lib\devices*, therefore you could lose your device if you reinstall.

An exported device is stored in a .zip file and saved in the user's My Documents directory (typically *username\My Documents*).

Making Device Connections

The configuration of all peripherals, except UART, can be inspected in the emulator main window. The configuration of UART is defined by the hardware configuration of the COM ports on your Windows XP or Windows 7 PC.

For more information on connecting to a UART Device, see "[Connecting to a UART Device](#)."

To open a serial port, such as COM1 or COM2, in Windows you can use the Device Address Manager. In application code, you can use `Connector.open("comm:COM1")`

Connecting to a UART Device

To utilize the Universal Asynchronous Receiver/Transmitter (UART) functionality, you need to create a configuration file (for example `UARTConfig.xml`). The configuration file defines the device ID and Name, and the Name must point to a real serial port name defined by the operating system. For example,

```
deviceaccess.uart.dev14.name = COM1
```

For an already opened UART, you can add it to the peripheral manager by calling `PeripheralManager.open` with the configuration object.

Finding Files in the Multiple User Environment

The Oracle Java ME SDK can be installed on a system running a supported operating system version. All users with an account on the host machine can access the SDK. This feature is called the Multiple User Environment.

Note: The Multiple User Environment supports access from several accounts. It does not support multiple users accessing the SDK simultaneously. See ["Switching Users."](#)

To support multiple users the SDK creates an installation directory that is used as a source for copying. This document uses the variable *work* to represent the SDK working directory and *installdir* to represent the Oracle Java ME SDK installation directory. Each user's personal files are maintained in a separate working directory named `javame-sdk` that has a subdirectory for each version installed.

- ["Installation Directories"](#)
- ["NetBeans User Directories"](#)

To locate logs, see ["Device Manager Logs"](#) and ["Device Instance Logs."](#)

Switching Users

Multiple users cannot run the SDK simultaneously, but, you can run the SDK from different user accounts on the SDK host machine. When you switch users, you must close the SDK and exit the Device Manager, as described in ["The Device Manager on Windows."](#) A different user can then launch the SDK and own all processes.

Installation Directories

The SDK directory structure conforms to the Unified Emulator Interface Specification (<http://www.oracle.com/technetwork/java/javame/documentation/uei-specs-187994.pdf>), version 1.0.2. This structure is recognized by all IDEs and other tools that work with the UEI.

The installation directory has the following structure:

- `bin`. The bin directory contains the following command line tools. The default location of the bin directory is:

`installdir\bin`

- `cref`. The Java Card Platform Simulator tool, which is used to simulate smart cards in the emulator. It is used for testing SATSA (JSR 177) applications with the Oracle Java ME SDK. For more information on SATAS, see [Chapter 20](#).
 - `device-address` is a tool for viewing, adding, and removing devices that the SDK is not able to discover automatically. See ["Manage Device Addresses \(device-address\)"](#)
 - `device-manager`. The Device Manager is a component that must be running when you work with Oracle Java ME SDK. After installation it starts as a service, and it automatically restarts every time your computer restarts. See ["Starting and Running Emulators."](#)
 - `emulator`. UEI compliant emulator. See ["Emulator Command Line Options."](#)
 - `jadtool`. Tool for signing MIDlets. See ["Sign MIDlet Suites \(jadtool\)."](#)
 - `mekeytool`. Management of ME keystores. See ["Manage Certificates \(MEKeyTool\)"](#).
 - `preverify`. The Java ME preverifier.
 - `device-editor`. Tool for creating new custom devices. See ["Creating a Custom Device."](#)
 - `update-center`. The Oracle Java ME SDK Update Center.
 - `wma-tool`. A command line tool for sending and receiving SMS, CBS, and MMS messages. See ["Running WMA Tool."](#)
 - `wscompile`. Compiles of stubs and skeletons for JSR 172. See ["Generate Stubs \(wscompile\)"](#).
- `docs`. Release documentation.
 - `legal`. License and copyright files.
 - `lib`. JSR JAR files for compilation.
 - `runtimes`. CDC, CLDC, and IMP-NG runtime files.
 - `toolkit-lib`. Oracle Java ME SDK files for configuration and definition of devices and UI elements. Executables and configuration files for the Device Manager and other SDK services and utilities.

NetBeans User Directories

These are the default NetBeans user directories.

- NetBeans default project location:
`username\My Documents\NetBeansProjects`
- To see the NetBeans user directory, click the **Help** menu and select **About** in the main window. The default location is:
`username\.netbeans\3.4`

Oracle Java ME SDK Directories

This documentation sometimes uses *username* to represent the root location of user files.

- The `javame-sdk` directory contains device instances and session information. If you delete this directory, it is re-created automatically when the Device Manager is restarted.

`username\javame-sdk\3.4`

- Device working directories

`username\javame-sdk\3.4\work\devicename`

The named subdirectories each correspond to an emulation device, as described in [Table 8–1](#). Any detected external devices are also added to this directory space.

Device detection is described in ["Adding an External Device."](#)

Table 8–1 Device Names

Device	Platform	Emulator #
ClamshellJavaMEPhone1	CLDC	0
DefaultCdcPbpPhone1	CDC	1
IMPNGDevice1	CLDC	2
IMPNGDevice2	CLDC	3
Qualcomm_IoE_Device	CLDC	4
JavaMEPhone1	CLDC	5
JavaMEPhone2	CLDC	6
VgaAGUIPhone1	CDC	7
VgaCdcPhone1	CDC	8

- Device instances (device definitions).

`install\dir\toolkit-lib\process\device-manager\device-adapter`

This directory contains the bean files for the adapter categories. The beans in this directory and subdirectories determine whether a skin is visible in the Device Selector, among other things. You should not manipulate these files directly.

See ["Using the Custom Device Editor"](#) for instructions on creating your own custom skin.

- Both default skins and custom skins created with the Custom Device Editor are represented in the device-adapter directory.

Note: Do not manipulate custom skin files from the operating system. All custom skin activity should take place in the Custom Device Editor.

Profiling Applications

The Oracle Java ME SDK supports performance profiling for Java ME applications. The profiler keeps track of every method in your application. For a particular emulation session, it figures out how much time was spent in each method and how many times each method was called.

The SDK supports offline profiling. Data is collected during the emulation session. After you close the emulator you can export the data to a `.nps` file you can load and view later. As you view the snapshot you can investigate particular methods or classes and save a customized snapshot (a `.png` file) for future reference.

You can start a profiling session from the NetBeans IDE, as described in ["Collecting and Saving Profiler Data in the IDE"](#) or from the command line, as discussed in ["Command Line Profiling."](#) It is important to understand that profiling data produced from the command line has a different format (`*.prof`) than data produced from the NetBeans profiler (a `.nps` file).

Note: This feature might slow the execution of your application.


Profiling data from Oracle Java ME SDK projects is displayed in a tab in the IDE. The NetBeans IDE has a Profiling window (**Window > Profiling > Profiler**) but it is not discussed here. Because only performance profiling is supported, the Profiler window has limited usefulness for Java ME applications.

Collecting and Saving Profiler Data in the IDE


This procedure describes interactive profiling. To run profile an application from the command line, see ["Command Line Profiling."](#)

Note: The profiler maintains a large amount of data, so profiled MIDlets place greater demands on the heap. To increase the Heapsize property, see ["Setting Device Properties."](#)

1. In the Projects widow, right-click the project you want to profile and select Profile. If this is the first time profiling this project you are prompted to integrate the profiler. Click **Yes** to perform the integration.

Figure 9–1 Profiling of AudioDemo

The profiler attaches. You are prompted for the running options. Click **Yes**.


Figure 9–2 Attaching the Profiler

Check the **CPU Profiler**, and optionally check Profile System Classes. Press **Run**.

The emulator opens with your application running.

2. Interact with the application MIDlet(s) as you normally would.

The data is automatically displayed in a tab labeled `cpu:time`, where *time* is the time the data was displayed.

Figure 9–3 The Profiling Tab with Combined View Selected

3. To export the profile data, press the Export icon and supply a .nps file name and location. This data can be reloaded at a later time. See ["Loading a .nps File."](#)

Figure 9–4 Exporting Profile Data

4. To save the current view to a .png file, press the "Save current view to image" icon and supply a file name and location.

Figure 9–5 Saving the Current View

Loading a .nps File

A previously exported .nps file ("[Collecting and Saving Profiler Data in the IDE](#)") can be loaded at a later time.

Follow these steps to retrieve profile data:

1. Click the **Profile** menu and select **Load Snapshot...**
2. Select the .nps file.

The Profiler opens in its own tab labeled `cpu:filename`. Click the Info tab at the bottom of the Method table to view the snapshot.

Note: The profiling values obtained from the emulator do not reflect actual values on an external device.

Importing a .prof File

A .prof file created from the command line ("[Command Line Profiling](#)") can be loaded from the NetBeans IDE. The following example shows what a command line profiling session command might look like:

```
emulator.exe -Xdevice:JavaMEPhone1  
-Xdescriptor:"C:\Documents and Settings\username\My Documents\NetBeansProjects\UIDemo\dist\Games.jad" -Xprofile:file=C:\temp\UIDemo.prof
```

Files created from the command line are formatted differently from the .nps files created as described in "[Collecting and Saving Profiler Data in the IDE](#)."

Follow these steps to retrieve command line profile data from the IDE:

1. Click the **File** menu and select **Open File...**
2. Browse to the .prof file you want and click Open.

The Profiler displays the data in its own tab labeled `cpu:filename`.

When the file has been loaded it can be saved in the .nps format. Click the Export to... icon and supply a file name and location.

Network Monitoring

MIDP applications, at a minimum, are capable of HTTP network connections, but many other types of network connections are also possible. The network monitor provides a convenient way to see the information your application is sending and receiving on the network. This is helpful if you are debugging network interactions or looking for ways to optimize network traffic.

Networking monitoring works for emulators only (it is not supported for external devices).

- ["Monitor Network Traffic"](#)
- ["Filter or Sort Messages"](#)
- ["Save and Load Network Monitor Information"](#)
- ["Clear the Message Tree"](#)


Monitor Network Traffic

Follow these steps to activate the network activity for an application.

1. In the Projects window, right-click a project and select Profile.
2. If this is the first time profiling this application you are prompted to integrate the profile with the project. Click **Yes** to perform the integration.

In the Profile window, select **Network Monitor**, and click **Run**.


Figure 10–1 *Activating Network Activity*



3. Start your application.

When the application makes any type of network connection, information about the connection is captured and displayed in the Network Monitor tab.

Figure 10–2 The Network Monitor Tab



The top frame displays a list of messages. Click a message to display its details in the bottom frame.

In the Hex View, message bodies are shown as raw hexadecimal values with the equivalent text.

Note: You can examine messages that are still in the process of being sent. Incomplete messages are indicated by bold highlighting in the message tree.

You can view information up to a specific delimiter or back to a previous delimiter by clicking the Find Previous(Shift+F3) Occurrence or Find Next Occurrence(F3) icons in the Toolbar (between the Find Results and Clear Inactive Connection icons).

Filter or Sort Messages

Filters are useful for examining some subset of the total network traffic.

- In the [Select Devices] list check only the devices you want to view.
- In the [Select Protocols] list check only the protocols you want to view. The protocols listed reflect what is currently installed on the device.
- Click the magnifying glass in the Network Monitor Toolbar to search for a specific string in the data in the Phone or URL columns.

Time. Messages are sorted in chronological order of time sent or received.

URL. Messages are sorted by URL address. Multiple messages with the same address are sorted by time.

Click on a table header to sort the message data.

Save and Load Network Monitor Information

To save your network monitor session, click the Save Snapshot or Save As a Snapshot icon at the left of the Network Monitor Toolbar.

Figure 10–3 *The Network Monitor Toolbar*



Select a file name. The default file extension is .nmd (network monitor data).

Follow these steps to load a network monitor session:

1. Click the **File** menu and select **Open File...**
2. Browse to the .nmd file you saved.

Note: To avoid memory issues, the Hex view display is currently limited to 16kB of data.

Clear the Message Tree

To remove all inactive protocol records from the network monitor select the clear icon (the broom icon on the right of the Network Monitor Toolbar).

Monitoring Memory

This chapter describes how to use tracing and the memory monitor to examine an application's memory use on a particular device.

Activating tracing for a particular device enables you to see low-level information as an application runs.

The Memory Monitor shows memory use as an application runs. It displays a dynamic detailed listing of the memory usage per object in table form, and a graphical representation of the memory use over time. You can take a snapshot of the memory monitor data. Snapshots can be loaded and examined later.

Note: The memory use you observe with the emulator is not exactly the same as the memory use on an external device. Remember, the emulator does not represent an external device. It is one possible implementation of its supported APIs.

Enabling Tracing

Follow these steps to enable tracing.

1. In the Device Selector window, right-click a device and select **Properties**.
2. In the Properties window, go to the Monitor node and check the desired trace options.
 - **Trace GC** (garbage collection). Monitoring GC can help you determine object health. The garbage collector cannot delete objects that do not have a null reference. Dead objects will be garbage collected and not reported as live.
 - **Trace Class Loading**. Observing class initialization and loading is useful for determining dependencies among classes.
 - **Trace Exceptions**. Display exceptions caught.
 - **Trace Method Calls**. Reports methods called and returned. The output for this option is very verbose and it can affect performance.
3. (Optional) Verbose tracing output might cause you to run out of memory on the device before the application is fully tested. You can increase the device memory as follows:

Right-click a device and select **Properties**. From the General node, select Heapsize, and select a size.

Tracing data is displayed in the output window (**Window > Output > Output**) when an application is run on this device. It is also written to the device log, which is stored in the working directory for the device. For example:

```
username\javame-sdk\3.4\work\JavaMEPhone1\device.log
```

Using the Memory Monitor

Follow these steps to examine an application's memory use.

WARNING: Do not suspend the emulator while using the memory monitor.

1. In the Projects view, right-click the project and select **Profile**.
 - If the profiler is not yet integrated you are prompted to enable profiling for the project. Click **Yes** to continue.

The Profile window opens.

- Select **Memory Monitor**, and click **Run**.

The output window tab is labeled "memory-monitor" indicating that the memory monitor is active for this session. The output window displays both application status and tracing outputs for this device.

The memory monitor opens.

2. Interact with the application as usual.

In the Memory Monitor tab you see data displayed on the graph above and in the object table below.


To the left of the graph you see the Current memory use in bytes. The green line plots these values. The red line is the maximum amount of memory used since program execution, corresponding to the Maximum size in bytes on the left.

The object table columns are as follows:

- **Name.** Object class name.
- **Total.** Total number of objects allocated since the application began. The percentage given is the number of objects allocated over the total number of objects.
- **Total Size.** Total amount of memory the object uses in bytes. The percentage value is the amount of memory used over the total amount of memory.
- **Average Size.** Average object size in bytes, calculated by dividing the number of live instances by the total size.

Beneath the table you see counters displaying the total number of objects, the amount of memory used, the amount of free memory, and the total amount of memory on the device.

Figure 11–1 The Memory Monitor Tab



3. Interact with the object table while the memory monitor is running.
 - Click a column header to sort the data. The sorting is case sensitive.
 - Click a row to display the call stack tree in a window to the right of the table.
 - Click a folder to browse the call stacks tree to see the methods that create the object.
 - To find a particular method in the call stacks tree, click **Find** and enter a search string.
 - Click **Refresh** to update the call stacks tree as data is gathered. It is not refreshed automatically.

4. Take a snapshot of the memory monitor. Because the data changes rapidly it is convenient to take several snapshots and review them later.

Click the "Save session to file" icon above the graph and specify a file name and location for the monitor data. The automatically supplied extension is `.mms`.

5. Exit the application.

Some applications contain multiple MIDlets.

- When you exit a MIDlet the table data is cleared.
- The graph data is not cleared when you exit a MIDlet. The graph data you see is cumulative for this emulator session. The memory monitor plots session data for any MIDlet run on the current emulator until you exit the application and close the emulator.

Viewing a Session Snapshot

Follow these steps to reload a memory monitor snapshot.

1. Click the **File** menu and select **Open File...**
2. Browse to an `.mms` file you saved.

The memory monitor opens in its own tab in the main window. Note the tab displays the time the snapshot was taken.

Security and MIDlet Signing

MIDP 2.1 (JSR 118) includes a comprehensive security model based on protection domains. MIDlet suites are installed into a protection domain that determines access to protected functions. The MIDP 2.1 specification also includes a recommended practice for using public key cryptography to verify and authenticate MIDlet suites.

The general process to create a cryptographically signed MIDlet suite is as follows:

1. The MIDlet author, probably a software company, buys a signing key pair from a certificate authority (the CA).
2. The author signs the MIDlet suite with the signing key pair and distributes their certificate with the MIDlet suite.
3. When the MIDlet suite is installed on the emulator or on a device, the implementation verifies the author's certificate using its own copy of the CA's root certificate. Then it uses the author's certificate to verify the signature on the MIDlet suite.
4. After verification, the device or emulator installs the MIDlet suite into the security domain that is associated with the CA's root certificate.

For definitive information, consult the MIDP 2.1 specification at:

<http://download.oracle.com/otndocs/jcp/midp-2.1-mrel-oth-JSpec>

See the following topics:

- "Security Domains"
- "Setting Security Domains"
- "Signing a Project"
- "Managing Keystores and Key Pairs"
- "Managing Root Certificates"

Security Domains

The SDK supports the following security domains:

`minimum`. All permissions are denied to MIDlets in this domain.

`maximum`. All permissions are granted to MIDlets in this domain. Maximum is the default setting.

`unidentified_third_party`. Provides a high level of security for applications whose origins and authenticity cannot be determined. The user is prompted frequently when the application attempts a sensitive operation.

identified_third_party. Intended for MIDlets whose origins were determined using cryptographic certificates. Permissions are not granted automatically, but the user is prompted less often than for the unidentified_third_party domain.

operator. All permissions are denied to MIDlets in this domain.

manufacturer. Intended for MIDlet suites whose credentials originate from the manufacturer's root certificate.

Setting Security Domains

In the SDK, when you use **Run Project via OTA**, your packaged MIDlet suite is installed directly into the emulator where it is placed in a security domain. The emulator uses public key cryptography to determine the appropriate security domain.

- If the MIDlet or MIDlet suite is not signed, it is placed in the default security domain.
- If the MIDlet or MIDlet suite is signed, it is placed in the protection domain that is associated with the root certificate of the signing key's certificate chain. See ["Signing a Project."](#)

If your project is a MIDlet suite, the entire suite is signed (the individual MIDlets contained within are not).

Specify the Security Domain for an Emulator

1. In the Device Selection window, right-click on the device and select **Properties**.
2. Find the Security Domain setting and make a selection from the context menu.

The SDK knows the runtimes the device can support and supplies only possible domains. The default setting for the sample projects is Maximum.

Specify the Security Domain for a Project

1. Right-click a project and select **Properties**.
2. In the Category area, select Running (the green triangle).
3. Select Regular Execution and check the Security Domain box.

In this context regular execution means you are running in the emulator, as opposed to running OTA.

4. Select the domain from the drop-down menu.

Signing a Project

Devices use signing information to check an application's source and validity before allowing it to access protected APIs. For test purposes, you can create a signing key pair to sign an application. The keys are as follows:

- A private key that is used to create a digital signature, or certificate.
- A public key that anyone can use to verify the authenticity of the digital signature.

You can create a key pair with the Keystores Manager as described in ["Managing Keystores and Key Pairs."](#)

Sign a CLDC Project With a Key Pair

Follow these steps to sign a CLDC project with a key pair:

1. Right-click a project and select **Properties**.
2. From the Build category, select Signing.
3. Check the Sign Distribution checkbox.
4. Select a keystore from the Keystores drop-down menu, or click **Open Keystores Manager** to create a keystore.

The Certificate Details area displays the Subject, Issuer, and Valid (validity dates for the selected keystore) information.

5. Select a key pair alias from the drop-down menu.

A keystore might be accessed by several key pairs, each with a different alias. If you prefer to use a unique key pair, select Open Keystores Manager and create a new key pair. See ["Create a Keystore."](#)

6. Click **OK**.

See ["Obfuscating."](#)

Sign a CDC Project

To sign a CDC project use the JDK `jarsigner` command from the command line. For example:

```
jarsigner.exe -keystore keystore.ks -storepass keystorepwd MyCdcApp.jar dummyCA
```

Managing Keystores and Key Pairs

For test purposes, you can create a signing key pair to sign a MIDlet. The Keystores Manager administers this task, as described in the remainder of this topic, the key pair consists of two keys:

- A private key that is used to create a digital signature, or certificate.
- A public key anyone can use to verify the authenticity of the signature.

To deploy on a device, you must obtain a signing key pair from a certificate authority recognized by the device. You can also import keys from an existing Java SE platform keystore.

The following topics describe the user interface:

- ["Security Domains"](#)
- ["Create a New Key Pair"](#)
- ["Remove a Key Pair"](#)
- ["Import an Existing Key Pair"](#)

You can also use the command line tools described in ["Command Line Security Features."](#)

Working With Keystores and Key Pairs

The Keystores Manager handles creating and using keystores. The keystores known to the Keystores Manager are listed when you sign a project, as described in ["Signing."](#)

Keystores contain key pairs, which you can also manage from this dialog. You must select a keystore to access the key pair tools.

- [Section , "Security Domains"](#)
- [Section , "Create a New Key Pair"](#)
- [Section , "Remove a Key Pair"](#)
- [Section , "Import an Existing Key Pair"](#)

Create a Keystore

1. Select the **Tools** menu and select **Keystores**.
The Keystores Manager opens.
2. Click **Add Keystore....**
The Add Keystores window opens.
3. Select **Create a New Keystore**.
4. Supply a name, location, and password.
5. Click **OK**.
The new keystore appears in the Keystores list.

Add an Existing Keystore

1. Select the **Tools** menu and select **Keystores**.
The Keystores Manager opens.
2. Click **Add Keystore....**
The Add Keystores window opens.
3. Select **Add Existing Keystore**.
4. Browse to the location of the keystore and select the keystore file. The default location for user-defined keystores is:
username
5. Select a keystore and Click **Open**, then click **OK**.
The existing keystore appears in the Keystores list. You might have to unlock this keystore, and each key pair within it.

Create a New Key Pair

1. Select the **Tools** menu and select **Keystores**.
The Keystores Manager opens.
2. Select a Keystore in the Keystores area on the left. If you prefer a different keystore, you can create one as described in "[Create a Keystore](#)."
Note, you cannot add a key to the Built-in Keystore, but you can export a key from it.
3. Click the **New...** button.
4. Fill in the Create Key Pair dialog:
You must provide an alias to refer to this key pair.

The six Certificate Details fields are provisionally optional. You must complete at least one field.

Key Pair Alias. The name used to refer to this key pair.

Common Name. Common name of a person, such as "Jane Smith"

Organization Unit. Department or division name, such as "Development"

Organization Name. Large organization name, such as "Oracle Corporation"

Locality Name. Locality (city) name, such as "Santa Clara"

State Name. State or province name, such as "California"

Country. Two-letter country code, such as "US"

Although not required, you should provide a password. The password should be at least six characters long.

5. Click **OK**.

The new key is displayed in the Keys area under its alias. You can now select this keypair when you sign a project. See ["Signing a Project."](#)

Remove a Key Pair

1. Select the **Tools** menu and select **Keystores**.
2. In the Keys area, click a Key Pair.
3. Select **Delete**. You are asked if you are sure. Click **Yes** if you are and the delete proceeds.

Import an Existing Key Pair

If you have keys in a Java SE platform keystore that you would like to use for MIDlet signing, you can import the signing keys to the Oracle Java ME SDK.

1. Select the **Tools** menu and select **Keystores**.
2. Click **Add Keystore....**
The Add Keystore window opens.
3. Click **Add Existing Keystore**.
4. Browse to the keystore location.
5. Click **OK**.

Managing Root Certificates

The Oracle Java ME SDK command line tools described in ["Manage Certificates \(MEKeyTool\)"](#) manage the emulator's list of root certificates.

External devices have similar lists of root certificates, although you typically cannot modify them. When you deploy your application on an external device, you must use signing keys issued by a certificate authority whose root certificate is present on the device. This makes it possible for the device to verify your application.

Each emulator instance has its own `_main.ks` file located in its `appdb` directory. For example: `username\javame-sdk\3.4\work\devicename\appdb`.

You can use the `-import` option to import certificates from these keystores as described in ["Manage Certificates \(MEKeyTool\)."](#)

Command Line Reference

This topic describes how to operate the Oracle Java ME SDK from the command line and details the command line tools required to build and run an application.

- "Run the Device Manager"
- "Manage Device Addresses (device-address)"
- "Emulator Command Line Options"
- "Build a Project from the Command Line"
- "Packaging a MIDlet Suite (JAR and JAD)"
- "Command Line Security Features"
- "Generate Stubs (wscompile)"

Run the Device Manager

The Device Manager is a component that runs as a service. It detects devices (real or emulated) that conform to the Unified Emulator Interface Specification (<http://www.oracle.com/technetwork/java/javame/documentation/uei-specs-187994.pdf>), version 1.0.2. The Device Manager automatically restarts every time you use the SDK. You can manually launch the Device Manager from a script or a command line.

`installdir\bin\device-manager.exe`

To see a log of activities, launch the Device Manager with the `-XenableOutput` option.

Manage Device Addresses (device-address)

`installdir\bin\device-address` is a tool for viewing, adding, and removing devices that the SDK is not able to discover automatically. The Microsoft device emulator is an example of such a device. The syntax is:

Table 13–1 Device Address Commands

Command	Action
<code>add address_type address</code>	Add the specified address.
<code>del address_type address</code>	Delete the specified address.
<code>list</code>	List all addresses.
<code>list address_type</code>	List the addresses of the specified type.

For example, the following command adds a device:

```
installdir\bin\device-address.exe add ip 192.168.1.2
```

Emulator Command Line Options

You can launch the emulator independent of the GUI using `bin\emulator`. The syntax is as follows:

```
emulator options
```

The general options are as follows:

Table 13–2 *Emulator Commands*

Command	Action
<code>-classpath path</code>	Specifies a search path for application classes. The path consists of directories, ZIP files, and JAR files separated by semicolons.
<code>-cp path</code>	
<code>-D property=value</code>	Sets a system property value.
<code>-help</code>	Display a list of valid options.
<code>-version</code>	Display version information about the emulator.
<code>-Xdevice:devicename</code>	Run an application on the emulator using the given device instance name.
<code>-Xquery</code>	Print emulator skin information on the standard output stream and exit immediately. The information includes the skin name, screen size, and other capabilities.

This is a simple example of running the emulator from the command line:

```
emulator.exe -Xdescriptor:C:\Java_ME_platform_SDK_3.4\apps\Games\dist\Games.jad  
-Xdevice:JavaMEPhone2
```

MIDlet Options

Options for running MIDlets in the emulator are as follows:

- `-Xautotest:JAD-file-URL`

Run in autotest mode. This option installs a MIDlet suite from a URL, runs it, removes it, and repeats the process. The purpose is to run test compatibility kits (TCKs) with the emulator, using a test harness such as JT Harness or Java Device Test Suite (JDTs).

For example:

```
emulator -Xautotest:http://localhost:8080/test/getNextApp.jad
```

Given the above command, `-Xautotest` causes the emulator to repeatedly install, run, and remove the first MIDlet from the MIDlet suite provided through the HTTP URL. When the emulator starts, it queries the test harness, which then downloads and installs the TCK MIDletAgent.

- `-Xdescriptor:jad-file`

Install a MIDlet, run it, and uninstall it after it finishes.

- `-Xdomain:domain-name`

Set the MIDlet suite's security domain.

The `Xjam` argument runs an application remotely using the Application Management Software (AMS) to run over-the-air (OTA) provisioning. If no application is specified with the argument, the graphical AMS is run.

- `-Xjam[:install=<JAD-file-url> |force|list|storageNames|run=[<storageNames>|<StorageNumber>]|remove=[<storage name>|<storage number> | all]]`

Installs the application with the specified JAD file onto a device.

- `force`. If an existing application has the same storage name as the application to be installed, `force` removes the existing application before installing the new application.
- `list`. List all the applications installed on the device and exit. The list is written to standard output before the emulator exits.
- `storageNames`. List all applications installed on the device. The list is written to standard output before the emulator exits. Each line contains one storage name in numerical order. The list contains only the name so the order is important. For example the first storage name must be storage number 1.
- `-Xjam:run=[<storage-name> | <storage-number>]`

Run a previously installed application. The application is specified by its valid storage name or storage number.

- `-Xjam:remove=[<storage-name> | <storage-number> | all]`

Remove a previously installed application. The application is identified by its valid storage name or storage number. If `all` is supplied, all previously installed applications are removed.

- `-Xjam:transient=jad-file-url`

If specified, `transient` is an alias for installing, running, and removing the application with the specified JAD file.

- `-Xprofile[:system=<y/n>, file=file]`

Profile the application's CPU usage.

- `system`. Whether to profile system classes. Default value is `n` (only user classes are profiled).
- `file`. CPU profiler snapshot is stored to the specified file, `%d` in file name is replaced by snapshot number. If not specified, profiler data is not stored to a file, it is passed to a connected profiler if one is present.

This example illustrates OTA installation:

```
emulator -Xjam:install=http://www.myserver.com/apps/MyApp.jad
        -Xdevice:JavaMEPhone2
```

The above command returns the ID of the installed application. When you obtain the ID you can run it with: `emulator=Xjam:run=ID`

See ["Emulator Command Line Options"](#) and ["Debugging and Tracing Options."](#)

CDC Options

The following options apply to CDC projects.

- `-Xmain:main-class-name`

Run the main method of a Java class, as in Java SE.

- `-Xxlet:classpath=class-path, class=fully-qualified-name, [arg=argument]` *

Run an Xlet application.

See ["Emulator Command Line Options"](#) and ["Debugging and Tracing Options."](#)

Debugging and Tracing Options

You can use the following options with the emulator for debugging and tracing CLDC projects.

- `-Xdebug`

Enable runtime debugging. The `-Xrunjdpw` option must be called to support `-Xdebug`.

- `-Xrunjdpw:debug-settings`

Start a Java debug wire protocol session, as specified by a list of comma-separated debug settings. Both `-Xrunjdpw` and `-Xdebug` must be called.

Valid debug settings include the following:

- `transport=transport-mechanism` - Transport mechanism used to communicate with the debugger. The only transport mechanism supported is `dt_socket`.
- `address=host:port` - Transport address for the debugger connection. If *host* is omitted, *localhost* is assumed to be the host machine.
- `server={y | n}` - Starts the debug agent as a server. The debugger must connect to the port specified. The possible values are *y* and *n*. Currently, only *y* is supported (the emulator must act as a server).
- `suspend={y | n}` - The possible values are *y* and *n*.

When `suspend` is set to *n*, the application starts immediately and the debugger can be attached at any time during its run.

When `suspend` is set to *y*, the application does not start until a debugger attaches to the debugging port and sends a resume command, so an application can be debugged from the very beginning.

This example shows debugging:

```
emulator.exe -Xdevice:JavaMEPhone1 -Xdebug -Xrunjdpw:transport=dt_socket,suspend=n, server=y,address=51307 -Xdescriptor:..\apps\Games\dist\Games.jad -Xdomain:maximum
```

With the emulator running you can attach a debugger.

- To attach a graphical debugger from NetBeans, select **Debug > Attach Debugger**.
- A sample command would be:

```
jdk/bin/jdb -connect  
com.sun.jdi.SocketAttach:hostname=localhost,port=51307
```

Command Line Profiling

To add profiling to an emulator session, use:

```
-Xprofile:[system=<y | n>], file=filename.prof
```

For example:

```
emulator.exe -Xdevice:JavaMEPhone1
-Xdescriptor:"C:\username\My Documents\NetBeansProjects\Games\dist\Games.jad"
-Xprofile:file=C:\temp\Games.prof
```

When you launch the emulator and profile an application from the command line the data profile you save has a different format than .nps files created with the Profile option in the NetBeans IDE.

Files created from the command line should be given the extension .prof to distinguish them from IDE profiler files.

To view .prof files in the IDE, select **Profile > Java ME > Import CPU Profiler Snapshot...** Your file is displayed in a tab labeled with the name of the file containing the snapshot.

When the file is loaded in the IDE you can export the data in .nps form, using the Export to... feature as described in ["Collecting and Saving Profiler Data in the IDE,"](#) Step 5. These files can be loaded using **Profile > Java ME > Import CPU Profiler Snapshot...**

Build a Project from the Command Line

In the user interface, building a project is a single step. Behind the scenes, however, there are two steps. First, Java source files are compiled into Java class files. Next, the class files are *preverified*, which means they are prepared for the CLDC VM. See the following topics:

- ["Check Prerequisites"](#)
- ["Compile Class Files"](#)
- ["Preverify Class Files"](#)

Check Prerequisites

Before building and running an application from the command line, verify that the jar command is in your path. To find the version of the development kit, run java -version at the command line.

Compile Class Files

Use the javac compiler from the Java SE development kit to compile Java source files. You can use the existing Oracle Java ME SDK project directory structure. Use the -bootclasspath option to tell the compiler to use the MIDP APIs, and use the -d option to tell the compiler where to put the compiled class files.

The following example demonstrates how you might compile a MIDP 2.1 application, taking source files from the src directory and placing the class files in the tmpclasses directory. Newlines have been added for clarity.

```
javac -target 1.3 -source 1.3
      -bootclasspath ..\..\lib\cldc_10.jar;..\..\lib\midp2.1.jar
      -d tmpclasses
      src\*.java
```

For more information on javac, consult the Java SE documentation.

Preverify Class Files

The next step is to preverify the class files. The `bin` directory of the Oracle Java ME SDK includes the `preverify` utility. The syntax for the `preverify` command is as follows:

```
preverify files | directories
```

Some of the options are as follows:

Table 13–3 Options to `preverify` Command

Name	Description
<code>-classpath classpath</code>	Specify the directories or JAR files (given as a semicolon-delimited list) from which classes are loaded.
<code>-d output-directory</code>	Specify the target directory for the output classes. This directory must exist before preverifying. If this option is not used, the preverifier places the classes in a directory called <code>output</code> .

Following the example for compiling, use the following command to verify the compiled class files. As before, newlines are added for clarity.

```
preverify.exe
-classpath ..\..\lib\cldcapi10.jar;..\..\lib\midpapi20.jar
-d classes
tmpclasses
```

As a result of this command, preverified class files are placed in the `classes` directory. If your application uses WMA, MMAPI, or other versions of CLDC or MIDP, be sure to include the relevant `.jar` files in the classpath.

Packaging a MIDlet Suite (JAR and JAD)

To package a MIDlet suite manually you must create a manifest file, an application JAR file, and finally, a MIDlet descriptor (also known as a Java Application Descriptor or JAD).

Create a manifest file containing the appropriate attributes as specified in the MIDP specification. You can use any text editor to create the manifest file. For example, a manifest might have the following contents:

```
MIDlet-1: My MIDlet, MyMIDlet.png, MyMIDlet
MIDlet-Name: MyMIDlet
MIDlet-Vendor: My Organization
MIDlet-Version: 1.0
MicroEdition-Configuration: CLDC-1.1
MicroEdition-Profile: MIDP-2.1
```

Create a JAR file containing the manifest and the suite's classes and resource files. To create the JAR file, use the `jar` tool that comes with the Java SE software development kit. The syntax is as follows:

```
jar cfm file manifest -C class-directory . -C resource-directory .
```

The arguments are as follows:

- *file* - JAR file to create.
- *manifest* - Manifest file for the MIDlets.
- *class-directory* - Directory containing the application's classes.

- *resource-directory* - Directory containing the application's resources.

For example, to create a JAR file named `MyApp.jar` whose classes are in the `classes` directory and resources are in the `res` directory, use the following command:

```
jar cfm MyApp.jar MANIFEST.MF -C classes . -C res .
```

Create a JAD file containing the appropriate attributes as specified in the MIDP specification. You can use any text editor to create the JAD file. This file must have the extension `.jad`.

Note: You must set the `MIDlet-Jar-Size` entry to the size of the JAR file created in the previous step.

For example, a JAD file might have the following contents:

```
MIDlet-Name: MyMIDlet
MIDlet-Vendor: My Organization
MIDlet-Version: 1.0
MIDlet-Jar-URL: MyApp.jar
MIDlet-Jar-Size: 24601
```

Command Line Security Features

The full spectrum of the Oracle Java ME SDK's security features are also available from the command line. You can adjust the emulator's default protection domain, sign MIDlet suites, and manage certificates.

- ["Change the Default Protection Domain"](#)
- ["Sign MIDlet Suites \(jadtool\)"](#)
- ["Manage Certificates \(MEKeyTool\)"](#)

Change the Default Protection Domain

To adjust the emulator's default protection domain, use the following option with the emulator command:

```
-Xdomain:domain-type
```

Assigns a security domain to the MIDlet suite. Enter an appropriate security domain as described in ["Security Domains."](#) For example, `-Xdomain:maximum`.

Sign MIDlet Suites (jadtool)

`jadtool` is a command-line interface for signing MIDlet suites using public key cryptography according to the MIDP 2.1 specification. Signing a MIDlet suite is the process of adding the signer certificates and the digital signature of the JAR file to a JAD file. `jadtool` is also capable of signing payment update (JPP) files.

`jadtool` only uses certificates and keys from Java SE platform keystores. Java SE software provides `keytool`, the command-line tool to manage Java SE platform keystores.

`jadtool` is packaged in a JAR file. To run it, open a command prompt, change the current directory to `install\bin`, and enter the following command:

```
jadtool command
```

The commands are as follows:

- `-help`
Prints the usage instructions for `jadtool`.
- `-addcert -alias key alias [-storepass password] [-keystore keystore] [-certnum number] [-chainnum number] [-encoding encoding] -inputjad filename -outputjad filename`
Adds the certificate of the key pair from the given keystore to the JAD file or JPP file.
- `-addjarsig [-jarfile filename] -keypass password -alias key alias -storepass password] [-keystore keystore] [-chainnum number] [-encoding encoding] -inputjad filename -outputjad filename`
Adds a digital signature of the input JPP file to the specified output JPP file.
- `-showcert [<[-certnum number] [-chainnum number]> | [-all]] [-encoding encoding] -inputjad filename`
Displays information about certificates in JAD files.

The default values are as follows:

- `-encoding` - UTF-8
- `-jarfile` - MIDlet-Jar-URL property in the JAD file
- `-keystore` - `$HOME\.keystore`
- `-certnum` - 1
- `-chainnum` - 1

Manage Certificates (MEKeyTool)

MEKeyTool manages the public keys of certificate authorities (CAs), making it functionally similar to the `keytool` utility that comes with the Java SE SDK. The purpose of the keys is to facilitate secure HTTP communication over SSL (HTTPS).

Before using MEKeyTool, you must first have access to a Java Cryptography Extension keystore. You can create one using the Java SE `keytool` utility (found in the `\bin` directory for your JDK).

To run MEKeyTool, open a command prompt, change the current directory to `installdir\bin`, and enter the following command:

```
installdir\bin\mekeytool.exe -command
```

The command keywords follow.

The Oracle Java ME SDK contains a default ME keystore named `_main.ks`, which is located in:

```
installdir\runtimes\cldc-hi\appdb
```

This keystore includes all the certificates that exist in the default Java SE platform keystore that comes with the Java SE installation.

Also, each emulator instance has its own `_main.ks` file located in `username\javame-sdk\3.4\work\devicename\appdb`. If you do not specify a value for MEkeystore, a new key is added to the default ME key for this emulator instance.

If you do not specify a value for `-keystore`, the default keystore is used:

username\keystore.ks

- **-help**
Prints the usage instructions for MEKeyTool.
- **-import -alias *alias* [-keystore *JCEkeystore*] [-MEkeystore *filename*] [-storepass *storepass*] -domain *domain-name***
Imports a public key into the ME keystore from the given JCE keystore using the given Java Cryptography Extension keystore password. and the default Java Cryptography Extension keystore is *username\keystore*.
- **-list [-MEkeystore *filename*]**
Lists the keys in the ME keystore, including the owner and validity period for each.
- **-delete (-owner *owner* | -number *key-number*) [-MEkeystore *filename*]**
Deletes a key from the given ME keystore with the given owner.

Generate Stubs (wscompile)

Mobile clients can use the Stub Generator to access web services. The wscompile tool generates stubs, ties, serializers, and WSDL files used in Java API for XML (JAX) RPC clients and services. The tool reads a configuration file, that specifies either a WSDL file, a model file, or a compiled service endpoint interface. The syntax for the stub generator command is as follows:

`wscompile [options] configuration-files`

Table 13-4 lists the wscompile options:

Table 13-4 *wscompile Options*

Option	Description
-gen	Same as -gen:client
-gen:client	Generates client artifacts (stubs, etc.)
-import	Generates interfaces and value types only
-d <i>output directory</i>	Specifies where to place generated output files
-f: <i>features</i>	Enables the given features
-g	Generates debugging info
-features: <i>features</i>	Same as -f: <i>features</i>
-httpproxy: <i>host:port</i>	Specifies a HTTP proxy server (port defaults to 8080)
-model <i>file</i>	Writes the internal model to the given file
-O	Optimizes generated code
-s <i>directory</i>	Specifies where to place generated source files
-verbose	Outputs messages about what the compiler is doing
-version	Prints version information
-cldc1.0	Sets the CLDC version to 1.0 (default). Float and double become String.
-cldc1.1	Sets the CLDC version to 1.1 (float and double are OK)
-cldc1.0info	Shows all CLDC 1.0 information and warning messages.

Note: Exactly one `-gen` option must be specified. The `-f` option requires a comma-separated list of features.

Table 13–5 lists the features (delimited by commas) that can follow the `-f` option. The `wscompile` tool reads a WSDL file, compiled service endpoint interface (SEI), or model file as input. The Type of File column indicates which of these files is used with a particular feature.

Table 13–5 Command Supported Features (`-f`) for `wscompile`

Option	Description	Type of File
<code>explicitcontext</code>	Turns on explicit service context mapping	WSDL
<code>nodatabinding</code>	Turns off data binding for literal encoding	WSDL
<code>noencodedtypes</code>	Turns off encoding type information	WSDL, SEI, model
<code>nomultirefs</code>	Turns off support for multiple references	WSDL, SEI, model
<code>novalidation</code>	Turns off full validation of imported WSDL documents	WSDL
<code>searchschema</code>	Searches schema aggressively for subtypes	WSDL
<code>serializeinterfaces</code>	Turns on direct serialization of interface types	WSDL, SEI, model
<code>wsi</code>	Enables WSI-Basic Profile features (default)	WSDL
<code>resolveidref</code>	Resolves <code>xsd:IDREF</code>	WSDL
<code>donotunwrap</code>	No unwrap.	WSDL

Examples

```
wscompile -gen -d generated config.xml
wscompile -gen -f:nounwrap -O -cldc1.1 -d generated config.xml
```

Oracle Java ME SDK uses the log4j logging facility to manage Device Manager and Device Instance logs.

Logging levels are configurable.

Device Manager Logs

The Device Manager log is placed into:

`username\javame-sdk\3.4\log\device-manager.log`

You can configure logging levels in the following XML file:

`install\dir\toolkit-lib\process\device-manager\conf\log4j.xml`

A priority value for the categories `com.sun` or `VM` can be set to the following levels: FATAL, ERROR, WARN, INFO, DEBUG, TRACE (ordered from least to most verbose).

Example 14–1 Setting a Category Value

```
<category name="com.sun">
  <priority value="DEBUG"/>
  <appender-ref ref="CONSOLE-ALL"/>
  <appender-ref ref="FILE"/>
</category>

<category name="VM">
  <priority value="INFO"/>
  <appender-ref ref="CONSOLE-ALL"/>
  <appender-ref ref="FILE"/>
</category>
```

Device Instance Logs

Each device (or emulator) instance writes its own log in to its directory.

`username\javame-sdk\3.4\work\devicename\device.log`

log4j.xml controls the verbosity of the device instance logs, as described in "[Device Manager Logs](#)."

The Oracle Java ME SDK supports many standard Application Programming Interfaces (APIs) defined through the Java Community Process (JCP) program. JCP APIs are often referred to as JSRs, named after the Java Specification Request process. JSRs that are not part of the platform are referred to as "optional packages."

The CLDC/MIDP platform is based on the *Mobile Information Device Profile and Connected Limited Device Configuration* (JSRs 118 and 139).

The IMP-NG platform is based on *Information Module Profile - Next Generation (IMP-NG)* (JSR 228).

See [Table 15–1](#) for a full list of supported JCP APIs. The Oracle Java ME SDK provides documentation describing how certain APIs are implemented in the SDK. Many supported APIs do not require special implementation considerations, so they are not discussed in this help set. "[Oracle APIs](#)" describes Oracle APIs provided to support the IMP-NG platform.

For convenience the Javadocs that are the intellectual property of Oracle are in your installation's \docs directory. The remainder can be downloaded from <http://jcp.org>.

JCP APIs

Table 15–1 Supported JCP APIs

JSR, API	Name, URL
JSR 75, PIM and File	<i>PDA Optional Packages for the J2ME Platform</i> http://jcp.org/en/jsr/detail?id=75
JSR 82, Bluetooth and OBEX	<i>Java APIs for Bluetooth</i> http://jcp.org/en/jsr/detail?id=82
JSR 118, MIDP 2.1	<i>Mobile Information Device Profile</i> http://jcp.org/en/jsr/detail?id=118
JSR 135, MMAPI 1.1	<i>Mobile Media API</i> http://jcp.org/en/jsr/detail?id=135
JSR 139, CLDC 1.1	<i>Connected Limited Device Configuration</i> http://jcp.org/en/jsr/detail?id=139
JSR 172, Web Services	<i>J2ME Web Services Specification</i> http://jcp.org/en/jsr/detail?id=172

Table 15–1 (Cont.) Supported JCP APIs

JSR, API	Name, URL
JSR 177, SATSA	<i>Security and Trust Services API for Java ME</i> http://jcp.org/en/jsr/detail?id=177
JSR 179, Location	<i>Location API for Java ME</i> http://jcp.org/en/jsr/detail?id=179
JSR 184, 3D Graphics	<i>Mobile 3D Graphics API for J2ME</i> http://jcp.org/en/jsr/detail?id=184
JSR 205, WMA 2.0	<i>Wireless Messaging API</i> http://jcp.org/en/jsr/detail?id=205
JSR 209, AGUI 1.0	<i>Advanced Graphics and User Interface Optional Package for the J2ME Platform</i> http://www.jcp.org/en/jsr/detail?id=209
JSR 211, CHAPI	<i>Content Handler API</i> http://jcp.org/en/jsr/detail?id=211
JSR 217, PBP 1.1	<i>Personal Basis Profile 1.1</i> http://www.jcp.org/en/jsr/detail?id=217
JSR 218, CDC 1.1	<i>Connected Device Configuration 1.1</i> http://jcp.org/en/jsr/detail?id=218
JSR 226, SVG	<i>Scalable 2D Vector Graphics API for J2ME</i> http://jcp.org/en/jsr/detail?id=226
JSR 228, IMP-NG	<i>Information Module Profile - Next Generation (IMP-NG)</i> http://jcp.org/en/jsr/detail?id=228
JSR 234, AMMS	<i>Advanced Multimedia Supplements</i> http://jcp.org/en/jsr/detail?id=234
JSR 239	<i>Java Binding for OpenGL ES API</i> http://jcp.org/en/jsr/detail?id=239
JSR 256	<i>Mobile Sensor API</i> http://jcp.org/en/jsr/detail?id=256
JSR 257	<i>Contactless Communication API</i> http://jcp.org/en/jsr/detail?id=257
JSR 280, XML API	<i>XML API for Java ME</i> http://jcp.org/en/jsr/detail?id=280

Oracle APIs

The IMP-NG project type supports developing applications for the Oracle Java ME Embedded 3.4 runtime. The Java ME Embedded 3.4 runtime includes several standard JSR APIs and additional Oracle APIs for embedded use cases. These new APIs are:

- Device Access API
The Device Access API provides interfaces and classes for communicating with and controlling peripheral devices.
- Logging API

The Logging API provides a lightweight and extensible framework based on the concepts of the `java.util.logging` package, enabling applications to log messages in a variety of formats and using custom handlers.

- AMS API

The AMS API provides an interface to the application management capabilities of the runtime to allow authorized applications to interact with and extend the application management system.

- AccessPoint API

The AccessPoint API is an extension to the Generic Connection Framework and enables applications to select among multiple access points if the underlying platform provides more than one data access point.

The Javadocs for these APIs are in your installation's `\docs` directory.

JSR 75: PDA Optional Packages

The Oracle Java ME SDK supports JSR 75, the PDA Optional Packages (PDAP) for the J2ME Platform. JSR 75 includes two independent APIs:

- The `FileConnection` optional package allows MIDlets access to a local device file system.
- The Personal Information Management (PIM) optional package includes APIs for manipulating contact lists (address book), calendars, and to-do lists.

This chapter describes how the Oracle Java ME SDK implements the `FileConnection` and PIM APIs.

FileConnection API

On an external device, the `FileConnection` API typically provides access to files stored in the device's memory or on a memory card.

In the Oracle Java ME SDK emulator, the `FileConnection` API enables MIDlets to access files stored on your computer's hard disk.

The files that can be accessed using the `FileConnection` optional package are stored in the following subdirectory:

```
username\javame-sdk\3.4\work\devicename\appdb\filesystem
```

For example, the `JavaMEPhone1` emulator instance comes with a root directory installed named `root1`. Each subdirectory of `filesystem` is called a *root*. The Oracle Java ME SDK provides a mechanism for managing roots.

While the emulator is running, click the **Tools** menu and select **Manage File System**. The Manage File System dialog box opens.

In the Mounted File System Root Directories panel you can mount, unmount, or unmount and delete filesystem roots. Mounted roots are displayed in the top list, and unmounted roots are listed in the Unmounted File System Root Directories panel. You can remount or delete a selected directory. Mounted root directories and their subdirectories are available to applications using the `FileConnection` API. Unmounted roots can be remounted in the future.

- To add a new empty filesystem root directory, click **Mount Empty...** and fill in a name for the directory.
- To mount a copy of an existing directory, click **Mount Copy...**, and browse to select a directory you want to copy. When the File System Root Entry dialog opens, enter the name for this root. A deep copy of the selected directory is placed into the emulator's filesystem with the specified root name.

- To make a directory inaccessible to the FileConnection API, select it in the list and click **Unmount**. The selected root is unmounted and moved to the Unmounted roots list.
- To completely remove a mounted directory, select it and click **Unmount & Delete**.
- To remount an unmounted directory, select it and click **Remount**. The root is moved to the mounted roots list.
- To delete an unmounted directory, select it and click **Delete**. The selected root is removed from the list.

PIM API

The Oracle Java ME SDK emulator stores contact, calendar, and to-do information in standard files on your desktop computer's hard disk. All information is stored in:

```
username\javame-sdk\3.4\work\devicename\appdb\PIM
```

Each device instance has its own data. Lists are stored in subdirectories of the contacts, events, and todo directories. For example, a contact list called Contacts is contained in *installdir\appdb\PIM\contacts\Contacts*.

Inside the list directory, items are stored in vCard (.vcf) or vCalendar (.vcs) format (see <http://www.imc.org/pdi/>). Contacts are stored in vCard format, while calendar and to-do items are both stored in vCalendar format.

Running PDAPDemo

PDAPDemo shows how to use the PIM and FileConnection APIs that are part of the JSR 75 specification.

Browsing Files

The default emulators have one directory, root1. This directory is located at:

```
username\javame-sdk\3.4\work\devicename\appdb\filesystem\root1
```

For test purposes, copy files or even directories into root1. You can also add other directories at the same level as root1.

Now open and run the PDAPDemo project.

- Launch the FileBrowser MIDlet. You see a directory listing, and you can browse through the directories and files you have placed there.
- Select a directory and press the View soft button to enter it.
- Using the Menu commands you can view a file or see its properties. Try selecting the file and choosing Properties or View from the menu.

You can view the content of text files in the browser.

- Try using the External Events Generator to unmount and mount directories. Unmounted directories are not visible in the application running on the emulator.

The PIM API

The JSR75 PIM APIs example demonstrates how to access personal information, such as contact lists, calendars, and to-do lists.

- After you launch the example, select a type of list from the main menu.

In this example each type of list works the same way and each list type contains a single list. For example, if you select Contact Lists, there is a single contact list called Contacts. Event Lists contains a single list called Events, and To-Do Lists contains a single list named To Do.

- After you have selected a list type and chosen the specific list, you can view all the items in the list. If this is the first time you have run the example, the list might be empty.

- To add an item, select **New** from the menu. The application prompts you for a Formatted Name for the item.

To add more data fields to this item select **Add Field**. You see a list of field names. Pick as many as you like. You can fill in the fields at any time.

- To save the new item, select **Commit** from the menu.

To return to the list, select the Back command. You see the item you just created in the list.

The items that you create are stored in standard vCard or vCalendar format in this directory:

```
username\javame-sdk\3.4\work\devicename\appdb\PIM
```

The PIM API allows for exporting contact, calendar, and to-do items in a standard format. The exact format depends on the list type. When you are viewing an item in any list, the menu contains a command for viewing the exported item.

For example, when you are viewing a contact list item, the menu contains Show vCard. When you select this command, the exported item is shown on the screen. Calendar items and to-do items both get exported as vCalendar.

JSR 82: Bluetooth and OBEX Support

This chapter describes how the Oracle Java ME SDK implements the Bluetooth and OBEX APIs.

The Oracle Java ME SDK emulator supports JSR 82, the Java APIs for Bluetooth. The emulator is fully compliant with version 1.1 of the specification, which describes integration with the push registry. JSR 82 includes two independent APIs:

- The Bluetooth API provides an interface to Bluetooth wireless networking, including device discovery and data exchange.

The Oracle Java ME SDK emulator enables you to develop and test applications that use Bluetooth without having actual Bluetooth hardware. The SDK simulates a Bluetooth environment for running emulators. Multiple emulator instances can discover each other and exchange data using the Bluetooth API.

For an example, see ["Running the Bluetooth Demo."](#)

- The OBEX API allows applications to use the Object Exchange (OBEX) protocol over Bluetooth or other communication channels.

The Oracle Java ME SDK implements OBEX transfer over simulated Bluetooth and TCP connections.

For an example, see ["Running the OBEX Demo."](#)

Setting OBEX and Bluetooth Properties

The Oracle Java ME SDK enables you to configure the Bluetooth and OBEX simulation environment. Because the simulation requires a sender and receiver, Bluetooth settings are configured separately for each device. Follow these steps to set device properties:

1. In the device selector, right-click a CLDC device and select **Properties**.

The device properties are displayed in the Properties window. If you do not see this window, click the **Window** menu and select **Properties** from the NetBeans Toolbar.

2. Scroll down to see the Bluetooth and OBEX properties. When you click a property a description is shown in the description area. If you can not see this area, right click a property and select Show Description Area.

The System Properties can be retrieved in an application using the `getProperty()` method in `javax.bluetooth.LocalDevice`. The Bluetooth properties are fully described in the JSR 82 specification.

- **Bluetooth Enabled**

Enable or disable state of Bluetooth functionality

- **Bluetooth Address**
The Bluetooth address of this device
- **Friendly Name**
Human-readable name of the device
- **bluetooth.sd.trans.max**
The maximum number of concurrent service discovery transactions. The default is 8.
- **bluetooth.sd.attr.retrievable.max**
The maximum number of service attributes to be retrieved per service record. The default is 16.
- **bluetooth.master.switch**
Enable or disable a master or slave switch. Enabled by default.
- **bluetooth.l2cap.receiveMTU.max**
The maximum ReceiveMTU size in bytes supported in L2CAP. This is the maximum payload size this connection can accept.
The default value is 672.
- **OBEX Maximum Packet Length**
The default is 4096 bytes.
The maximum packet length affects how much data is sent in each packet between emulators. Shorter packet values result in more packets and more packet overhead.
- **Device is discoverable**
Enabled by default.
- **Authentication is enabled**
Enabled by default.
- **Encryption is enabled**
Enabled by default.
- **Authorization is enabled**
Enabled by default.

Running the Bluetooth Demo

This application contains MIDlets that demonstrate the use of JSR 82's Bluetooth API. It shows how images can be transferred between devices using Bluetooth.

You must run two emulator instances to see this process, and each device must have a different phone number.

1. Use JavaMEPhone1 to launch Bluetooth Demo, then launch Bluetooth Demo on JavaMEPhone2.
2. The demo gives you a choice of Server or Client.
3. On the first emulator, highlight Server and use the right softbutton to select **OK**.

The server starts and displays a list of images. At the beginning, none of the images are available on the Bluetooth network.

Select the image you want to make available.

Press Publish image (the right soft button). The icon color changes from purple to green, indicating it is published.

4. On the second emulator running the Bluetooth Demo, highlight Client and click **OK**. The MIDlet displays "Ready for images search." Click the **Find** soft button. The MIDlet finds the other emulator and gets a list of published images. Select one from the list and select Load.
 - If you are running the demonstration in a trusted protection domain, the image is transferred using simulated Bluetooth and is shown on the client emulator.
 - If you are not running in a trusted protection domain, the first emulator (the server) displays a prompt asking if you want to authorize the connection from the client. Select **Yes**. The image is displayed in the client emulator.

Running the OBEX Demo

This application shows how to transfer image files between emulator instances using the OBEX API. This demonstration shows the use of OBEX over a simulated infrared connection.

1. Launch two instances of the emulator. One listens for incoming connections, while the other attempts to send an image.

For example, right-click ObexDemo, select **Run With...** and select the device JavaMEPhone1. Repeat and select JavaMEPhone2.

2. In the first emulator, select Receive Image. (Depending on your security level, the application warns that an OBEX connection allows other devices to talk to yours and asks, "Is it OK to make the connection?" Select **Yes**.) Click **Start** to run the application. The listener emulator displays a screen reading "Waiting for connection."
3. In the second emulator (the sender), select Send Image and press the Start soft key. Select an image from the list and select Send. (Depending on your security level, the application warns that the demo wants to make an outgoing client connection, and asks if it is OK. Select **Yes**.) The Send Image utility uploads the image.
4. In the listening emulator, the utility displays information about the incoming image and asks "Would you like to receive it?" Select **Yes**.

The image you selected is transferred over the simulated infrared link and displayed on the first emulator.

JSR 135: Mobile Media API Support

JSR 135, the Mobile Media API (MMAPI), provides a standard API for rendering and capturing time-based media, like audio or video. The API is designed to be flexible given the media formats, protocols, and features supported by various devices.

See the following topics:

- ["Media Types"](#)
- ["MMAPI MIDlet Behavior"](#)
- ["Ring Tones"](#)
- ["Running AudioDemo"](#)
- ["Running MMAPI Demos"](#)

For information on programming with MMAPI, see the following:

The J2ME Mobile Media API:

<http://www.jcp.org/en/jsr/detail?id=135>

Media Types

The emulator's MMAPI implementation supports the following media types.

Table 18–1 Supported MIME Types

MIME Type	Description
audio/amr*	Adaptive Multi-Rate Narrow Band
audio/midi	MIDI files
audio/mpeg*	MP3 files
audio/mp4*	MP4 Audio files
audio/sp-midi	Scalable Polyphony MIDI
audio/x-tone-seq	MIDP 2.1 tone sequence
audio/x-wav*	WAV PCM sampled audio
image/gif	GIF 89a (animated GIF)
video/3gpp*	Third generation mobile broadband with video
video/mpeg*	MPEG video
video/mp4*	MP4 video files
video/avi*	Video capture emulation and Audio-Video Interleaved files

In the previous table, an asterisk (*) indicates a media type that requires corresponding DirectShow filters to be installed on your system. For example, MP3 support might require an MP3 Splitter and an MP3 Decoder (these might be two separate DirectShow filters, or they might be combined in one filter). You can use any appropriate filter, but Oracle Java ME SDK 3.4 has only been tested with filters from the K-Lite Mega Codec Pack 4.8.0. If no appropriate DirectShow filters are found on your system, JSR 135 Player creation for the media type might fail.

Media Capture

The Oracle Java ME SDK emulator supports audio and video capture. Audio capture is supported using the capture capabilities of the system upon which the emulator runs.

Video capture is supported by simulating a camera input.

Consult the `MMAPIDemo` example application for details and source code that demonstrates how to capture audio and video.

MMAPI MIDlet Behavior

MIDlets have a lifecycle that is defined in the MIDP specification. MIDlets can be paused by events such as incoming phone calls. A well-behaved MIDlet releases important device resources when it is paused and reallocates or restarts those resources when the MIDlet is resumed. In the MMAPI arena, stop any Players that are rendering content when a MIDlet is paused.

The Oracle Java ME SDK prints a message to the console if you pause a MIDlet and it does not stop its running Players. You can test this feature using the Pausing Audio Test MIDlet.

The warning message is printed only once for each running emulator.

Ring Tones

MMAPI plays ring tones, as demonstrated in "[Simple Tones](#)" and "[Simple Player](#)". The ring tone formats mentioned here are in common use. You can download ring tones or create your own.

Download Ring Tones

Ring tone files can be downloaded from many internet sites, including the following:

- <http://www.convertyourtone.com/>
- <http://www.phonezoo.com>

Ring Tone Formats

This section provides samples of several formats

- RTTTL, the Ringing Tones text transfer language format, is explained at http://en.wikipedia.org/wiki/Ring_Tone_Transfer_Language
- Nokia Composer

This is a rendition of Beethoven's 9th symphony in Nokia Composer format:

```
16g1,16g1,16g1,4#d1,16f1,16f1,16f1,4d1,16g1,16g1,16g1,16#d1,
```

16#g1,16#g1,16#g1,16g1,16#d2,16#d2,16#d2,4c2,16g1,16g1,16g1,
16d1,16#g1,16#g1,16#g1, 16g1,16f2,16f2,16f2,4d2

- Ericsson Composer

Beethoven's Minuet in G:

a b + c b + c b + c b + C p + d a B p + c g A
p f g a g a g a g A p b f G p a e F

Beethoven's 9th symphony theme:

f f f # C # d # d # d C p f f f # c # f #f # f f + # c + # c + # c # A
ff f c # f # f # f f + # d + # d + # d

- Siemens Composer Format

Inspector Gadget theme:

C2(1/8) D2(1/16) Dis2(1/8) F2(1/16) G2(1/8)
P(1/16) Dis2(1/8) P(1/16) Fis2(1/8) P(1/16)
D2(1/8) P(1/16) F2(1/8) P(1/16) Dis2(1/8)
P(1/16) C2(1/8) D2(1/16) Dis2(1/8) F2(1/16)
G2(1/8) P(1/16) C3(1/8) P(1/16) B2(1/2) P(1/4)
C2(1/8) D2(1/16) Dis2(1/8) F2(1/16) G2(1/8) P(1/16)
Dis2(1/8) P(1/16) Fis2(1/8) P(1/16) D2(1/8) P(1/16)
F2(1/8) P(1/16) Dis2(1/8) P(1/16) C3(1/8) B2(1/16)
Ais2(1/8) A2(1/16) Gis2(1/2) G2(1/8) P(1/16) C3(1/2)

- Motorola Composer

Beethoven's 9th symphony:

4 F2 F2 F2 C#4 D#2 D#2 D#2 C4 R2 F2 F2 F2 C#2 F#2 F#2
F#2 F2 C#+2 C#+2 C#+2 A#4 F2 F2 F2 C2 F#2 F#2 F#2 F2
D#+2 D#+2 D#+2

- Panasonic Composer

Beethoven's 9th symphony:

444** 444** 444** 1111* 4444** 4444** 4444** 111*
0** 444** 444** 444** 1111** 4444** 4444** 4444**
444** 11** 11** 11** 6666* 444** 444** 444** 111**
4444** 4444** 4444** 444** 22** 22** 22**

- Sony Composer

Beethoven's 9th symphony:

444****444****444****111#*****444#*****444#*****444#*****
111*****(JD)0000444****444****444****111#*****444#*****
444#*****444#*****444****11#*****11#*****11#*****666#*****
444****444****444****111****444#*****444#*****

444#****444****22#****22#****22#****

Running AudioDemo

Demonstrates audio capabilities, including mixing and playing audio with an animation. Select a MIDlet from the list, and from the menu, select 1, Launch.

- **Audio Player.** Select a sound clip and press the Play soft button. Click **Back** to return to the list of clips.
- **Bouncing Ball.** Select No Background and press the Play soft button. Two balls randomly bounce in the screen, emitting a tone whenever they contact a wall.
Wave background, tone seq background, and MIDI background play the same two-ball audio visual sequence with the additional audio background.
- **Mix Demo.** Select a MIDlet and press the **Play** soft button. This demo shows that different audio formats can play simultaneously.
Tone+Wav. The audio clip starts playing and the Tone soft button is displayed. Press the Tone button to hear a tone playing over the original audio clip.
Tone+ToneSeq - The audio clip starts playing and the Tone soft button is displayed. Press the Tone button to hear a tone playing over the original audio clip.
ToneSeq+Wav - The tone sequence and the wav sequence play simultaneously. Press the Pause soft button to interrupt, and press Play to resume.

Running MMAPIDemos

The MMAPIDemos application contains four MIDlets that showcase the SDK's multimedia capabilities.

Simple Tones

Simple Tones demonstrates how to use interactive synthetic tones. Select a sample, then click **Play** on the lower right.

- Short Single Tone and Long Single Tone use `Manager.playTone()` to play tones with different pitch.
- Short MIDI event plays a chord on the interactive MIDI device (locator "device://midi"). The `shortMidiEvent()` method of `MIDIControl` is used to trigger the notes of the chord.

To run the MMAPI Drummer demo, click or type number keys (0-9). Each number plays a different sound.

Simple Player

The Simple Player application demonstrates the range of audio and video capabilities of the emulator. It includes sample files in a variety of formats and can play files from the emulator's persistent storage or from HTTP URLs.

The player portion uses a generic `javax.microedition.media.Player` interface. The player displays duration, media time, and controls for running the media file. If metadata is available in a file, the player enables you to view the information, such as author and title. In the case of MIDI files, if karaoke text is present in the file, it displays on the screen during play. Graphical user interface controls can be viewed on

the display screen if applicable. You can access these controls by selecting one of the media samples in Simple Player, then pressing the Menu button to view and select the desired command.

Select **Simple Player** then click **Launch**. The demo includes the following media samples:

- Bong plays a short WAV file. You can adjust certain playback features, as described later in this document. The display shows the duration of the sound in *minutes:seconds.hundredths* of a second, for example 00:01.04. This audio sample is a resource file in the MIDlet suite JAR file.
- MIDI Scale plays a sample musical scale. The display shows the title of the selected music file, the duration of the song, the elapsed time during playback, and the current tempo in beats per minute (bpm). This MIDI file is stored in the MIDlet suite JAR file.
- Simple Ring Tone plays a short sequence of Beethoven's Fifth Symphony. The display shows the title of the selected music file, the duration of the song, the elapsed time in seconds and tenths of a second during playback, and the current tempo in beats per minute (bpm). This ring tone file (.jts format) is stored in the MIDlet suite JAR file.
- WAV Music plays a brief audio file. The display shows the title of the audio file, the duration of the audio the elapsed time during playback, and the playback rate in percent. This WAV file is retrieved from an HTTP server.
- MIDI Scale plays a MIDI file that is retrieved from an HTTP server.
- The Animated GIF example shows an animated GIF that counts from 1 to 5. The file is stored in the MIDlet suite JAR file.
- AMR Narrow band. Plays an Adaptive Multi-rate narrow band file. This sample requires an AMR codec. This sample was tested with the K-Lite Mega Codec Pack 4.8.0. This codec is freely downloadable.
- Audio Capture from a default device lets you capture audio from a microphone or connected device. The sound is captured and played back on the speaker. To avoid feedback, use a headset.
- Video Capture Simulation simulates viewing input video. For example, on a device equipped with a camera.
- [enter URL] Plays back media files from arbitrary HTTP servers. Type a valid URL at the insertion point and click OK to play a file. If you want to open an HTTP directory from which to select media, be sure to add a slash to the end of the URL.

In addition, Simple Player parses ring tones in Ringing Tones text transfer language (RTTTL). See <http://www.convertyourtone.com/rtttl.html> for information on RTTTL.

The Simple Player menu lists commands that control media playback.

The first menu item, Quick Help, displays a list of commands and actions mapped to keypad buttons. Some actions are not applicable for every media type.

The remaining menu items vary depending on the media type. Some actions, such as Rate, open a control with which you can arbitrarily change the playback. Click Back to return to the player screen and see or hear your changes.

Video

The Video application illustrates how the emulator is capable of playing animated GIF files and capturing video. On an external device with a camera, video capture shows the user what the camera sees.

Animated GIFs and video capture can be implemented using either a `Form Item` or a `Canvas`. The Video demonstration includes all the possibilities.

- **Animated GIF - Form [jar]** shows an animated GIF in a `Form`. A simple indicator shows the progress through the animation. The form also includes some information about the playback, including the current time.
- **Animated GIF - Canvas [jar]** shows an animated GIF in a `Canvas`. A simple indicator shows the progress through the animation.
- **Video Capture - Form** simulates capturing video from a camera or other source and showing it as an `Item` in a `Form`. Select **Snapshot** to take a snapshot of the captured video. The snapshot is placed beneath the video capture for comparison.
- **Video Capture - Canvas** simulates capturing video from a camera or other source and showing it in a `Canvas`. Select **Snapshot** to get a still image of the current appearance. The snapshot is shown briefly, then the display goes back to the video capture.

Pausing Audio Test

This test MIDlet demonstrates the proper use of `pauseApp()` and the alternative.

WARNING: Do not run the memory monitor while using this demo.

In the Well-Behaved case suspending uses `pauseApp()` to close the player and remembers the length of time the audio file played. When the player resumes, it starts playing the audio file at the point that it was suspended.

In the Not Well-Behaved case the player is stopped instead of suspended. When the player is restarted the audio file plays from the beginning.

Test the two cases as follows:

- Run MMAPIDemos, and launch Pausing Audio Test.
The music starts playing. The initial value of Current State is Well-Behaved.
- Select **Application > Suspend** (or F5), to pause the music.
- Select **Application > Resume** (or F6) to resume playing the audio clip from the stopping point.
- Click the Misbehave soft key.
- Select **Application > Suspend** (or F5), to stop the music.
- Select **Application > Resume** (or F6). The player restarts but the clip plays from the beginning.

JSR 172: Web Services Support

The Oracle Java ME SDK emulator supports JSR 172, the J2ME Web Services Specification. JSR 172 provides APIs for accessing web services from mobile applications. It also includes an API for parsing XML documents.

See the following topics:

- ["Generating Stub Files from WSDL Descriptors"](#)
- ["Creating a New Mobile Web Service Client"](#)
- ["Run JSR172Demo"](#)

Generating Stub Files from WSDL Descriptors

The NetBeans IDE provides a stub generator that automates creating source code for accessing web services that conform to the J2ME Web Services Specification. You can add stubs to any MIDP application.

Note: If you are using NetBeans 7.1.2, or 7.2.1 or higher the "SOAP Web Services" plugin must be installed and activated.

The following is a general procedure for adding stubs:

1. In the Projects window, expand the tree for a project.
2. Launch the Java ME Web Service Client wizard:

Right-click the Source Packages node and select **New > Other** and select the CLDC category, then select **Java ME Web Service Client...**

3. In the New Java ME Webservice Client page, you can do one of the following actions:
 - Click **Running Web Service** and enter the URL for the WSDL and then click **Retrieve WSDL**.
 - Click **Specify the Local filename for the retrieved WSDL** and browse to a file on your system.

In either case, you must enter a package name (if it is not supplied), then click **Finish**. The new package appears in the project and includes an interface file and a stub file.

4. You can now edit your source files to call the content the stub provides, then build and run.

See ["Creating a New Mobile Web Service Client"](#) for a step by step process, or see ["Run JSR172Demo"](#) and view the demo source files.


Creating a New Mobile Web Service Client

This sample procedure creates a new project and adds a web service client. However, you can add a web service client to any MIDP project, it does not have to be new.

If you are using a proxy server, you must configure the emulator's proxy server settings as described in ["Configuring the Web Browser and Proxy Settings."](#)


1. Click the **File** menu and select **New Project**, select the Java ME category, and the Mobile Application project type, and click **Next**.

Figure 19–1 *Creating a New Project and Adding a Mobile Application*



2. Name your project and check **Create Default Package** and **Main Executable Class**. Click **Next**. Be sure to create Hello MIDlet for this example.

Figure 19–2 *Creating the Main Executable Class*



3. Ensure that Oracle Java ME SDK is the platform and select a device. Click **Next**.

4. Right-click on the Source Packages node and select **New > Java ME Web Service Client...**
5. In the New Java ME Webservice Client page:
 - Click **Running Web Service** and in the WSDL URL field, enter:
<http://www.xmlme.com/WSShakespeare.asmx?WSDL>
 Click **Retrieve WSDL**.
 - The Package name is wsshakespeare.
 Click **Finish**.

Note: Many additional project options can be found under the New --> Other menu item.

Figure 19–3 The Java ME Web Service Client Information Dialog Box

Java ME Web Service Client Information

Select the source of the WSDL description for the web service to be added to this project.

☒ Running Web Service

WSDL URL:

Specify the local filename for the retrieved WSDL.

Local Filename:

☐ Existing WSDL File

WSDL Filename:

Client Name:

Project:

Package:

Created File:

☐ Generate DataBinding structures

The new package appears in the Source Packages tree and includes Shakespeare.java and Shakespeare_Stub.java.

6. Edit HelloMIDlet.java as follows:
 - At the beginning, replace the default import declarations with:


```
import javax.microedition.lcdui.*;
import javax.microedition.midlet.*;
import wsshakespeare.*;
```

- Locate the `startApp()` method and replace its contents with the following code:

```
String text;
Shakespeare s = new Shakespeare_Stub();
try {
    text = s.getSpeech("Romeo");
} catch (java.rmi.RemoteException rex) {
    text = "error";
    System.out.println(rex.getMessage());
}
TextBox t = new TextBox("Hello", text, 2048, 0);

final Command exitCommand = new Command("Exit", Command.EXIT, 1);
t.addCommand(exitCommand);
t.setCommandListener(new CommandListener() {
    public void commandAction(Command c, Displayable d) {
        if (c == exitCommand) {
            notifyDestroyed();
        }
    }
});

Display.getDisplay(this).setCurrent(t);
```

7. Build and run the project. You see a quote from Shakespeare's Romeo and Juliet on the device screen.

You can vary the above procedure to use a local WSDL file. Open the following web page in a browser:

<http://www.xmlme.com/WSShakespeare.asmx?WSDL>

Save it to a local file. For example, `C:\ws\WSShakespeare.wsdl`. Follow the procedure above, except at Step 4, specify the local file name.

Run JSR172Demo

JSR172Demo shows how to access a web service from a MIDlet. The web service in this demo is running on an Internet server, and it conforms to the J2ME Web Services Specification. The client is the MIDlet running in the emulator

If you are using a proxy server, you must configure the emulator's proxy server settings as described in ["Configuring the Web Browser and Proxy Settings."](#)

Set Up the GlassFish Server

This demo requires the Oracle GlassFish server.

- If you installed a full version of NetBeans you probably have a GlassFish installation. Select **Tools > Servers** and select Glassfish to view the defaults.
- If you do not have Glassfish, it can be downloaded from:

<http://www.oracle.com/technetwork/java/javaee/downloads>

Set Up Environment Variables

Set the following environment variables:

`JAVA_HOME=Java-installation-path`

`GLASSFISH_HOME=GlassFish-installation-path`

Run the Demo Scripts

The scripts in the `\server` subdirectory assume that your server has a domain named "domain1" in which the service is automatically deployed. If you do not have a domain named domain1, set up this domain or edit `run.bat` and specify a domain you already have. Run the scripts:

```
demo_directory\JSR172Demo\server\build.bat
```

```
demo_directory\JSR172Demo\server\run.bat
```

Verify the Web Service

- Start the Glassfish service.
- In a browser, open the following URL:

```
http://localhost:8080/serverscript/serverscript
```

You see a page titled Web Services that displays information about the service including links to the WSDL file corresponding to the localhost url.

Run the MIDlet in the Emulator

JSR172Demo contains a single MIDlet named Server Script. Launch it and follow the prompts. You can browse through fictitious news headlines, all of which are retrieved from the web service.

JSR 177: Smart Card Security (SATSA)

The Security and Trust Services APIs (SATSA) provide smart card access and cryptographic capabilities to applications running on small devices. JSR 177 (the SATSA specification) defines four distinct APIs as optional packages:

- **SATSA-APDU** - Enables applications to communicate with smart card applications using a low-level protocol.
- **SATSA-JCRMI** - Provides an alternate method for communicating with smart card applications using a remote object protocol.
- **SATSA-PKI** - Enables applications to use a smart card to digitally sign data and manage user certificates.
- **SATSA-CRYPTO** - A general-purpose cryptographic API that supports message digests, digital signatures, and ciphers.

The Oracle Java ME SDK emulator fully supports SATSA. This topic describes how you can use the Oracle Java ME SDK to work with SATSA in your own applications.

For a more general introduction to SATSA and using smart cards with small devices, see the *SATSA Developer's Guide*, which is available at:

<http://www.oracle.com/technetwork/index.html>

If you must develop your own Java Card applications, download the Java Card Development Kit, available at:

<http://www.oracle.com/technetwork/java/javame/index.html>

This kit is for Windows.

Card Slots in the Emulator

Real SATSA devices are likely to have one or more slots that house smart cards. Applications that use SATSA to communicate with smart cards must specify a slot and a card application.

The Oracle Java ME SDK emulator is not an external device and, therefore, does not have physical slots for smart cards. Instead, it communicates with a smart card application using a socket protocol. The other end of the socket might be a smart card simulator or it might be a proxy that talks with real smart card hardware.

The Oracle Java ME SDK emulator includes two simulated smart card slots. Each slot has an associated socket that represents one end of the protocol that is used to communicate with smart card applications.

The default card emulator host name is localhost, and the default ports are 9025 for slot 0 and 9026 for slot 1. These port defaults are a property of the device. To change

the defaults in the user interface, right click on the device in the Device Selector, and select Properties. By default the Properties window is docked on the upper right of the Oracle Java ME SDK interface.

You can also change the port values in the device's property file found at:

```
username\javame-sdk\3.4\work\devicename
```

Edit the `device.properties` file and modify this line:

```
runtime.internal.com.sun.io.j2me.apdu.hostsandports =  
localhost:9025,localhost:9026
```

```
start cref -p 9025 -i memory_image.eeprom
```

For detailed instructions on running Mohair, see

Adjusting Access Control

Access control permissions and PIN properties can be specified in text files. When the first APDU or Java Card RMI connection is established, the implementation reads the ACL and PIN data from the `acl_slot-number` in the `workdir\devicename\appdb` directory. For example, an access control file for slot 0 might be:

```
username\javame-sdk\3.4\work\devicename\appdb\acl_0
```

If the file is absent or contains errors, the access control verification for this slot is disabled.

The file can contain information about PIN properties and application permissions.

Specifying PIN Properties

PIN properties are represented by a `pin_data` record in the access control file.

Example 20–1 PIN Properties Example

```
pin_data {  
    id number  
    label string  
    type      bcd | ascii | utf | half-nibble | iso  
    min       minLength  
    max       maxLength  
    stored    storedLength  
    reference byte  
    pad       byte - optional  
    flag       case-sensitive | change-disabled | unblock-disabled  
              needs-padding | disable-allowed | unblockingPIN  
}
```

Specifying Application Permissions

Application permissions are defined in access control file (`acf`) records. The record format is as follows:

Example 20–2 Access Control File Record Format

```
acf AID fnumbers separated by blanks {  
    ace {  
        root CA name  
        ...
```

```

    apdu {
        eight numbers separated by blanks
        ...
    }
    ...
    jcrmi {
        classes {
            classname
            ...
        }
        hashModifier string
        methods {
            method name and signature
            ...
        }
    }
    ...
    pin_apdu {
        id number
        verify | change | disable | enable | unblock
        four hexadecimal numbers
        ...
    }
    ...
    pin_jcrmi {
        id number
        verify | change | disable | enable | unblock
        method name and signature
        ...
    }
    ...
}

```

The `acf` record is an Access Control File. The AID after `acf` identifies the application. A missing AID indicates that the entry applies to all applications. The `acf` record can contain `ace` records. If there are no `ace` records, access to an application is restricted by this `acf`.

The `ace` record is an Access Control Entry. It can contain `root`, `apdu`, `jcrmi`, `pin_apdu`, and `pin_jcrmi` records.

The `root` record contains one CA name. If the MIDlet suite was authorized using a certificate issued by this CA, this `ace` grants access to this MIDlet. A missing `root` field indicates that the `ace` applies to all identified parties. One principal is described by one line. This line must contain only the word `root` and the principal name, for example:

```
root CN=thehost;OU=JCT;O=dummy CA;L=Santa Clara;ST=CA;C=US
```

The `apdu` or `jcrmi` record describes an APDU or Java Card RMI permission. A missing permission record indicates that all operations are allowed.

An APDU permission contains one or more sequences of eight hexadecimal values, separated by blanks. The first four bytes describe the APDU command and the other four bytes are the mask, for example:

```

apdu {
    0 20 0 82 0 20 0 82
    80 20 0 0 ff ff 0 0
}

```

The Java Card RMI permission contains information about the hash modifier (optional), class list, and method list (optional). If the list of methods is empty, an application is allowed to invoke all the remote methods of interfaces in the list of classes, for example:

```
jcrmi {
    classes {
        com.sun.javacard.samples.RMIDemo.Purse
    }
    hashModifier zzz
    methods {
        debit(S)V
        setAccountNumber([B)V
        getAccountNumber()[B
    }
}
```

All the numbers are hexadecimal. Tabulation, blank, CR, and LF symbols are used as separators. Separators can be omitted before and after symbols { and }.

The `pin_apdu` and `pin_jcrmi` records contain information necessary for PIN entry methods, which is the PIN identifier and APDU command headers, or remote method names.

Access Control File Example

Example 20–3 Access Control File Example

```
pin_data {
    label    Unblock pin
    id       44
    type     utf
    min      4
    stored   8
    max      8
    reference 33
    pad      ff
    flag     needs-padding
    yflag    unblockingPIN
}
pin_data {
    label    Main pin
    id       55
    type     half-nibble
    min      4
    stored   8
    max      8
    reference 12
    pad      ff
    flag     disable-allowed
    flag     needs-padding
}

acf a0 0 0 0 62 ff 1 {
    ace {
        root CN=thehost;OU=JCT;O=dummy CA;L=Santa Clara;ST=CA;C=US

        pin_jcrmi {
```

```

        id 55
        verify enterPIN([B]S
        change changePIN([B]S
        disable disablePIN([B]S
        enable enablePIN([B]S
        unblock unblockPIN([B]S
    }
}

acf a0 0 0 0 62 ee 1 {
    ace {
        root CN=thehost;OU=JCT;O=dummy CA;L=Santa Clara;ST=CA;C=US

        pin_apdu {
            id 55
            verify 1 2 3 1
            change 4 3 2 2
            disable 1 1 1 3
            enable 5 5 5 4
            unblock 7 7 7 5
        }
    }
}

acf a0 0 0 0 62 3 1 c 8 1 {
    ace {
        root CN=thehost;OU=JCT;O=dummy CA;L=Santa Clara;ST=CA;C=US

        jcrmi {
            classes {
                com.sun.javacard.samples.RMIDemo.Purse
            }
            hashModifier xxx
            methods {
                setAccountNumber([B]V
                getBalance()S
                credit(S)V
            }
        }
    }
    ace {
        jcrmi {
            classes {
                com.sun.javacard.samples.RMIDemo.Purse
            }

            debit(S)V
            getAccountNumber()[B
        }
    }
}

acf a0 00 00 00 62 03 01 0c 02 01 {
    ace {
        root CN=thehost;OU=JCT;O=dummy CA;L=Santa Clara;ST=CA;C=US
        apdu {
            0 20 0 82 0 20 0 82
            80 20 0 0 ff ff 0 0
        }
    }
}

```

```
        }
        apdu {
            80 22 0 0 ff ff 0 0
        }
    }
}
acf a0 00 00 00 62 03 01 0c 02 01 {

    ace {
        apdu {
            0 20 0 82 ff ff ff ff
        }
    }
}

acf a0 00 00 00 62 03 01 0c 06 01 {

    ace {
        apdu {
            0 20 0 82 ff ff ff ff
        }
    }
}
```

Running the SATSA Demo

For the demo to work this project must reside in the Oracle Java ME SDK installation's \apps subdirectory. You must create the apps directory yourself

1. Click the **File** menu and select **New Project** and in the Categories window select **Samples > Java ME SDK 3.4** and single-click **SATSA Demos**. Click **Next**. Save the sample project in:

installdir\apps\SATSA Demos

Click **Finish**.

2. Right-click on the project, click **Properties** and then click the Running category. Enable Regular execution and check **Specify the Security Domain**. Select maximum from the list.
3. Start the instance(s) of cref from the command line.
4. Run the project.
5. click **Properties** and then click the Running category
6. start *installdir*\bin\cref -i *installdir*\apps\SATSA Demos\sat.eeprom
7. start *installdir*\bin\cref -p 9025 -i *installdir*\apps\SATSA Demos\pki.eeprom
8. lick **Properties** and then click the Running category. Enable Regular execution and check **Specify the Security Domain**
9. start *installdir*\bin\cref -p 9025 -i *installdir*\apps\SATSA Demos\demo2.eeprom

JSR 179: Location API Support

The JSR 179 Location API gives applications the opportunity to use a device's location capabilities. For example, some devices include Global Positioning System (GPS) hardware. Other devices might be able to receive location information from the wireless network. The Location API provides a standard interface to location information, regardless of the underlying technique.

In the Location API, a *location provider* encapsulates a positioning method and supplies information about the device's location. The application requests a provider by specifying required criteria, such as the desired accuracy and response time. If an appropriate implementation is available, the application can use it to obtain information about the device's physical location.

The Oracle Java ME SDK includes a simulated location provider. You can use the emulator's External Events Generator to specify where the emulator should think it is located. In addition, you can configure the properties of the provider itself, and you can manage a database of landmarks.

Setting the Emulator's Location at Runtime


You can specify the simulated location of the emulator while it is running. In the emulator, click the **Tools** menu and select **External Events Generator**. Click the Location tab.

In the Location area of the tab, you can fill in values for the latitude, longitude, altitude, speed, and course. Applications that use the Location API can retrieve these values as the location of the emulator.

For more elaborate testing, you can set up a location script that describes motion over time. Location scripts are XML files consisting of a list of locations, called *waypoints*, and associated times. The Oracle Java ME SDK determines the current location of the emulator by interpolating between the points in the location script. Here, for example, is a simple location script that specifies a starting point (`time="0"`) and moves to a new point in ten seconds:

Example 21–1 Location Script Example

```
<waypoints>
  <waypoint time="0"
    latitude="14" longitude="50" altitude="310" />
  <waypoint time="10000"
    latitude="14.5" longitude="50.1" altitude="215" />
</waypoints>
```

Figure 21–1 External Events Generator Location Tab

The altitude measurement is in meters, and the time values are in milliseconds.

Use a text editor to create your location script. You can load it into the external event window by pressing the Browse button next to the Script field. Immediately below are controls for playing, pausing, stopping, and moving to the beginning and end of the location script. You can also drag the time slider to a particular point.

Some devices are also capable of measuring their orientation. To make this kind of information available to your application, change the State field in the Orientation box to Supported and fill in values for azimuth, pitch, and roll. The Magnetic Orientation check box indicates whether the azimuth and pitch measurements are relative to the Earth's magnetic field or relative to true north and gravity.

To test how your application handles unexpected conditions, try changing the State field in the Location Provider box to Temporarily Unavailable or Out of Service. When your application attempts to retrieve the emulator's location, an exception is thrown and you can see how your application responds.

Running the CityGuide Sample Project


CityGuide demonstrates how to use the Location API (JSR 179). It shows a walker's current position superimposed on a city map. The walker moves around the city and landmarks are highlighted and identified as the walker approaches. This demo gets the walker's location from an XML script named `citywalk.xml` (the event file) that submits the device location information.

Because location prompts occur frequently, it is best to run this demonstration in manufacturer (trusted) mode, as explained in the topic "Security Domains"[Security Domains](#)." In the user interface, right-click on your project and select the Running category. Select Specify the Security Domain, and select manufacturer or maximum.

1. Open and run the CityGuide project. In the emulator, launch the CityGuide MIDlet. The map page opens.
2. By default the display shows icons for four types of landmarks: restaurants, museums, shops, and theaters.

To adjust the landmark display (this is optional), open the soft menu and select the **Settings** command. Use the navigation keys to highlight a category, then use Select to check or uncheck an item. In the default skin, the item is selected when the square is filled with white.

Figure 21–2 The Location Settings Dialog Box



3. In the emulator, click the **Tools** menu and select **External Events Generator**. Click the Location tab, then click the Browse button. Select the event file from the directory containing the Citywalk application.

The player buttons at the bottom of the window are now active. Press the green play button (right-pointing triangle) to run the script.

4. When you are near a landmark its name appears at the top of the map. Open the soft menu and select the **Detail** command to see more information.

Figure 21–3 *The Landmark Detail Screen*



JSR 205: Wireless Messaging

The Oracle Java ME SDK supports the Wireless Messaging API (WMA) with a sophisticated simulation environment. WMA 1.1 (JSR 120) enables MIDlets to send and receive Short Message Service (SMS) or Cell Broadcast Service (CBS) messages. WMA 2.0 (JSR 205) includes all this and support for Multimedia Message Service (MMS) messages as well.

This chapter describes the tools you can use to develop WMA applications. It begins by showing how to configure the emulator's support of WMA. Next, it describes the WMA console, a tool for testing WMA applications.

Many of the tasks in this topic can also be accomplished from the command line. See ["Running WMA Tool."](#)

Using the WMA Console to Send and Receive Messages

The WMA console is a tool that enables you to send messages to and receive messages from applications that use JSR 205. You can, for example, use the WMA console to send SMS messages to a MIDlet running on the emulator.

See ["WMA Console Interface"](#) or ["Running WMA Tool."](#)

Launching the WMA Console


To launch the WMA console, select **Tools > Java ME > WMA Console**. Messages can be sent from the WMA Console to an emulator instance.

The console opens as a tab in the NetBeans documents area. The console phone number is displayed as part of the WMA Console tab label (for example, 987654321).

The WMA console phone number is an editable CLDC property. In the Device Selector, right-click the **CLDC, Java(TM) ME Platform SDK 3.4** node in the device selector, and select **Properties**. Type a new value in the WMA Console Phone Number field. If the number is available it is assigned to the console immediately. If the number is in use it is assigned to the console the next time you restart the NetBeans IDE.

WMA Console Interface

To open the WMA Output window, select **Window > Output > WMA Console Output**. This window displays messages received from an emulator. By default it is docked at the bottom of the NetBeans IDE.

Figure 22–1 WMA Console and Output Windows

Emulator Phone Numbers

Each instance of the emulator has a simulated phone number that is shown in the emulator window. The phone numbers are important because they are used as addresses for WMA messages. The phone number is a device property and it can be changed. In the device selector, right-click a device and view its properties.

Sending a Text or Binary SMS Message

To launch the WMA console, select **Tools > Java ME > WMA Console**. To open the WMA Output window, select **Window > Output > WMA Console Output**.

To send a text SMS message, click **Send SMS**.

- The To Clients window automatically lists the phone numbers of all running emulator instances. Select one or more destinations and enter a port number (the default is 50000, as described in ["WMADemo Push Registry Values"](#)).

- To send a text message, select the Text Message tab, type your message and click **Send**.
- To send the contents of a file as a binary message, click the Binary Message tab. Type in the path of a file directly, or click Browse to open a file chooser.

Note: The maximum message length for text and binary messages is 4096 bytes.

To try this yourself see ["Sending SMS Messages From WMA Console to an Emulator and Back."](#)

Sending Text or Binary CBS Messages

Sending CBS messages is similar to [Section , "Sending a Text or Binary SMS Message"](#) except that recipients are unnecessary because it is a broadcast.

To send a text or binary CBS message, click **Send CBS** in the WMA console. Specify a message identifier (see ["WMADemo Push Registry Values"](#)) and enter the text or binary content of your message. The maximum message length for text and binary messages is 4096 bytes.

Note: The emulator displays only the first 160 symbols of a received CBS message.

To try this yourself see ["Sending CBS Messages from WMA Console to an Emulator."](#)

Sending MMS Messages

MMS messages consist of one or more files, usually images or sounds. An MMS message can be sent to multiple recipients.

To send an MMS message from the WMA console, click the **Send MMS** button. The window for composing MMS messages has Header and Parts tabs.

- The header tab addresses the message.

The To area automatically lists one of the phone numbers from the running emulator instances. Click **Add** to select other available phone numbers from the drop-down list.

To remove a recipient, first select its line, then click **Remove**.

When a recipient is removed it must be added back manually. Click **Add** and a new line is added to the recipient table.

- To add optional media files (Parts) to the message, click the Parts tab and click **Add**. The maximum message length for text and binary messages is 4096 bytes.

Most media files have information to fill the Content Location, Content ID, Mime-Type (text/plain for simple MMS), and Encoding fields, but you can edit these fields as well. The default ID for the demo is `example.mms.MMSDemo` (see ["WMADemo Push Registry Values"](#)).

To remove a part, select it and press **Remove**.

To try this yourself, see ["Sending MMS Messages from WMA Console to an Emulator."](#)

Receiving Messages in the WMA Console

To start the WMA console, select **Tools > Java ME > WMA Console**. The WMA console window has its own phone number displayed on the WMA Console tab. You can send messages from your applications running on the emulator to the WMA console.

Received messages are displayed in the WMA output window.

Running WMADemo

The WMADemo sample project shows how to send and receive SMS, CBS, and MMS messages. Messages can be exchanged between emulator instances and can be generated or received using the WMA console utility.

WMADemo Push Registry Values

The push registry determines how the demo establishes certain types of connections. This information is set in the Application Descriptor. To view it, right-click the WMA Demo project and select Properties. In the Properties window, select the Application Description category and view the Push Registry tab.

- For SMS messages the port number is 50000.
- For CBS Messages, the Message Identifier is 50001.
- For MMS messages, the application ID is `example.mms.MMSDemo`.

Running WMADemo OTA

Because this sample uses the push registry, you cannot see all of its features with the regular execution process. You must install the application into the emulator using the over the air provisioning capability that mirrors how applications are installed on external devices.

1. Right-click the WMADemo project and select Properties from the context menu.
2. Select the Running Category and select the **Execute through OTA** option. Click **OK**.
3. Run WMADemo in an emulator.

Wait a few seconds for the application to download to the emulator and register itself.

The application home screen shows the MIDlets you can launch: SMS Send, SMS Receive, CBS Receive, MMS Send and MMS Receive.

4. Launch the WMA console (see ["Launching the WMA Console"](#)).

Sending SMS Messages From WMA Console to an Emulator and Back

In this demo you send messages between the WMA Console and the client demo application running on the emulator. Using the WMA console to send messages to the emulator exercises the push registry.

1. To launch the WMA console, select **Tools > Java ME > WMA Console**. To open the WMA Output window, select **Window > Output > WMA Console Output**. The WMADemo should be running in the emulator, as described in ["Running WMADemo OTA."](#)

2. Click the **Send SMS** button in the WMA console window.

Select the number that corresponds to the emulator. Typically, you check the box in front of 123456789. If you are not sure what number the emulator is using, look for a number above the emulator screen.

Fill in a port number of 50000. This is required because the demo waits for the SMS on that port.

Type your text message in the Message field and click **Send**.

3. The emulator asks if it is OK if the WMA Demo interrupts and if it can be started. You might receive several permission requests based on your firewall settings.

Select **Yes**. The SMSReceive MIDlet is launched and immediately displays the incoming SMS message.

4. To type a return message, press the Reply soft button. Type a message and select Send from the menu. You might be asked to give permission because there is a cost to your phone number. In the IDE, look in the WMA Output Window to confirm that your reply has been received. (The output window is typically displayed below the WMA Console. Be sure to click the WMA Output Window tab.)

Sending CBS Messages from WMA Console to an Emulator

This process is similar to sending SMS Messages. Instead of specifying a port number you specify a Message Identifier.

1. To launch the WMA console, select **Tools > Java ME > WMA Console**. To open the WMA Output window, select **Window > Output > WMA Console Output**.

2. Click the **Send** button in the WMA console window.

Supply a Message Identifier of 50001.

Type your text message or attach a binary message and click **Send**.

3. The emulator asks if it is OK if the WMA Demo interrupts and if it can be launched. You might receive several permission requests based on your firewall settings.

Select **Yes**. The CBSReceive MIDlet is launched and immediately displays the incoming message. Click **Exit** to close the MIDlet.

Sending MMS Messages from WMA Console to an Emulator

To send an MMS message from the WMA console to the emulator, ensure that WMA Demo has been installed using Run Project via OTA.

1. From the WMA Demo home screen, select MMS Receive. The emulator displays: "MMS Receive" and the message "Waiting for MMS on applicationID example.mms.MMSDemo..."
2. In the WMA console, click **Send MMS** to open the MMS composition window. The Header tab is open by default. Supply any message subject, the application ID `example.mms.MMSDemo`, and the telephone number of the running emulator. That number is displayed to the right of the To field by default. If you do not see the number you want, click the Add button to add it. When you have listed multiple numbers the number field is a dropdown list

The To field on the left is a dropdown list from which you can select To, Cc or Bcc.

3. Click the Parts tab. The WMA console enables you to select files to send as parts of the MMS message. Click **Add** and use the file browser to find the file you want to send. Click **OK**.
4. Click **Send** to send the message.

The image and its information are displayed in the emulator.

Running WMA Tool

WMA Tool is the command line version of the WMA Console. To send and receive SMS, CBS, and MMS messages from the command line, run:

```
install\dir\bin\wma-tool <command> [options]
```

The Device Manager must be running before you launch `wma-tool`.

When the tool is started, it outputs the phone number it is using.

Command

Each protocol has send and receive commands. The requested command is passed to the tool as a first argument. Possibilities are:

- `receive`
- `smsreceive` - receives SMS messages
- `cbsreceive` - receives CBS messages
- `mmsreceive` - receives MMS messages
- `smssend` - sends SMS message
- `cbssend` - sends CBS message
- `mmssend` - sends MMS message

The `*send` commands send the specified message and exit. The `*receive` commands print incoming messages until they are explicitly stopped.

Options

- o *outputDir*. Store binary contents to *outputDir*.
- t *timeout*. Non-interactive mode, waits the number of *timeout* seconds for messages.
- f Store text contents as files instead of printing them.
- q Quiet mode.

smsreceive, cbsreceive, and mmsreceive

The syntax for receiving a message is basically the same for all three protocols.

```
smsreceive [-o outputDir] [-t timeout] [-q]
```

```
cbsreceive [-o outputDir] [-t timeout] [-q]
```

```
mmsreceive [-o outputDir] [-t timeout] [-q]
```

Example

This example demonstrates how to receive a message from an emulator.

1. Start the emulator from the Windows Start menu:

Start > Programs > Java(TM) ME Platform SDK 3.4 > Java ME SDK CLDC Emulator.

You can also start the emulator from the bin directory. This example also runs the WMADemo project.

```
emulator.exe -Xdevice:JavaMEPhone1
-Xdescriptor:"C:\Documents and Settings\username\My Documents\NetBeansP
rojects\WMADemo\dist\WMADemo.jad"
```

2. Start wma-tool from the Oracle Java ME SDK *install*dir\bin directory:

```
C:\Java_ME_platform_SDK_3.4\bin\wma-tool smsreceive
```

```
WMA tool started with phone number: 987654321
press <Enter> to exit.
```

3. In the emulator run the SMS Send MIDlet and send a message to the WMA console. Enter the console telephone number

The console receives the message as follows:

```
SMS Received:
      From: 123456789
Timestamp: Thu Aug 23 23:31:26 PDT 2012
      Port: 50000
Content type: Text
      Encoding: GSM7BIT
      Content: A message from JavaMEPhone1 to wma-tool
Waiting for another message, press <Enter> to exit.
```

smssend

```
wma-tool smssend target_phone target_port message_content
```

- *target_phone*
Phone number of the target phone. Mandatory first argument.
- *target_port*
Port of the target phone. Mandatory second argument.
- *message_content*
Mandatory third argument. Can have one of these two forms:
 - text: text of the text message
 - -f *file*: sends content of the specified file as a binary message.

Example:

```
wma-tool smssend 123456789 50000 "smssend message from wma-tool"
```

cbssend

```
wma-tool cbssend message_id message_content
```

- *message_id*
ID of the message. Mandatory first argument.
- *message_content*

Mandatory second argument. Can have one of these two forms:

- `text`: text of the text message
- `-f file`: sends content of the specified file as a binary message.

Example:

```
wma-tool cbssend 50001 "cbssend message from wma-tool"
```

mmssend

```
wma-tool mmssend applicationId subject  
    [-to <targetphone>]* [-cc <target phone>]* [-bcc <target phone>]*  
    [-part { <part_from_file> | <part_from_text> } ]*
```

Each part is defined by `name=value` pairs delimited by a semicolon ";" separator.

Part Variables

To create `part_from_file`, define the following variables.

Note: The file and the mimeType must be separated by a semicolon.

- `file`
File to send as a message part.

- `mimeType`
Mime type of the file.

To create `part_from_text`, define the following variables:

- `text`
Text to send as a message part. mimeType is set to text/plain.
- `-to target_phone`
"to" target phone number. You can use any number of these options.
- `-cc target_phone`
"cc" target phone number. You can use any number of these options.
- `-bcc target_phone`
"bcc" target phone number. You can use any number of these options.

Part from Text Options

Separate options with semicolons. For example:

- `-part contentId=content ID; encoding=encoding; text=text`
Appends text part to the message. You can use any number of these options.
Contains the following options:
 - `content ID`: content ID of this message part
 - `encoding`: Sent text encoding. Only relevant for "text/plain." Mime type defaults to UTF8.

Part from File Options

`mimeType=mime type; contentId=content ID; file=file name`

- Appends binary part to the message with content loaded from the given file. You can use any number of these options.

Separate the options with a semicolon.

- *content id*: content ID of this message part
- *mime type*: mime type of this message part
- *file name*: file with content of this message part
- *fileEncoding*: Encoding of text in the file, only relevant for "text/plain", only applies if the file argument is present. Defaults to the value of the encoding variable.

Example:

```
wma-tool mmssend example.mms.MMSDemo MySubject -to 123456789 -part  
file=Duke.png;mimeType=image/png
```

JSR 184: Mobile 3D Graphics

The Mobile 3D Graphics API for J2ME, (JSR 184) provides 3D graphics capabilities with a low-level API and a high-level scene graph API. This chapter provides a brief overview and general guidelines for working with JSR 184.

JSR 184 is a specification that defines the Mobile 3D Graphics (M3G) API for the J2ME. This API provides 3D functionality in a compact package that's appropriate for CLDC/MIDP devices. The API provides two methods for displaying 3D graphics content:

- The *immediate mode* API makes it possible for applications to directly create and manipulate 3D elements.
- Layered on top of this is a *scene graph* API, also called *retained mode*, that makes it possible to load and display entire 3D scenes that are designed ahead of time.

For more information, consult the JSR 184 specification at <http://jcp.org/en/jsr/detail?id=184>.

Choosing a Graphics Mode

Applications are free to use whichever approach is most appropriate or to use a combination of the retained mode and immediate mode APIs.

JSR 184 provides a standard API for CLDC/MIDP devices, enabling a new generation of 3D applications. The immediate mode API, in turn, is compatible with OpenGL ES, a standard lightweight API for 3D graphics. See <http://khronos.org/> for more information on OpenGL ES.

Immediate Mode

Immediate mode is appropriate for applications that generate 3D graphics content algorithmically, such as scientific visualizations or statistical graphs. The application creates 3D objects and manipulates them directly.

For an example of immediate mode, see the `Life3D` MIDlet in the `Demo3D` example application.

Retained Mode

Most applications, particularly games, use the retained mode or scene graph API. In this approach, a graphic designer or artist uses 3D modeling software to create a scene graph. The scene graph is saved in the JSR 184 file format. The scene graph file is bundled with the application. At runtime, the application uses the scene graph API to load and display the file.

Applications can manipulate parts of a loaded scene graph to animate characters or create other effects. The basic strategy is to do as much work as possible in the modeling software. At runtime, the application can grab and manipulate parts of the scene graph, which can also include paths for animation or other effects.

For an example of retained mode, see the `retainedmode` MIDlet in the `Demo3D` example application.

Quality Versus Speed

One of the challenges of MIDP development is the constrained environment of typical devices. Compared to desktop computers, MIDP devices have slow processors and little memory. These challenges extend into the arena of 3D graphics. To accommodate a wide variety of implementations, the JSR 184 specification provides various mechanisms to make the display of a 3D scene as efficient as possible.

One approach is *scoping*, a technique where you tell the 3D graphics implementation when objects are not going to interact with each other. For example, if you defined a scene graph for a house, you could use scoping to specify that the light in the basement doesn't affect the appearance of the bedroom on the second floor. Scoping simplifies the implementation's task because it reduces the number of calculations required to show a scene.

In general, the best way to improve the rendering speed of 3D scenes is to make some compromises in quality. The Mobile 3D Graphics API includes *rendering hints* so that applications can suggest how the implementation can compromise quality to improve rendering speed.

Content for Mobile 3D Graphics

Most mobile 3D applications use scene graphs in resource files to describe objects, scenes, and characters. Usually it is not programmers but graphic designers or artists who create the scene graphs, using standard 3D modeling tools.

Several vendors offer tools for authoring content and converting files to the JSR 184 format.

Because it is relatively difficult to create and manipulate 3D graphics content in an application using the immediate mode API, most applications rely as much as possible on a scene graph file. By putting as much as possible into the scene graph file at design time, the application's job at runtime is considerably simplified.

Running Demo3D Samples

Demo3D contains MIDlets that demonstrate JSR 184 features.

Click the **File** menu and select **New Project**. In the Categories window, click **Samples** and select **Java ME SDK 3.4**. Then single-click **Demo3D** and click **Next**. Specify a name and location and click **Finish**.

Life3D

Life3D implements the popular Game of Life in three dimensions. Live cells are represented by cubes. Each cell has 26 possible neighbors (including diagonals). For each step of the animation, cells with fewer than four neighbors die of loneliness, while cells with more than five neighbors die of overcrowding. An empty cell with exactly four neighbors becomes a new live cell.

The view of the playing board rotates slowly so you can view the board from all angles.

The keypad buttons in [Table 23–1](#) provide control over the game:

Table 23–1 *Controls for Life3D*

Button	Description
0	Pause the animation.
1	Resume the animation at its default speed.
2	Speed up the animation.
3	Slow down the animation.
4	Select the previous preset configuration from an arbitrary list. The name of the configuration is shown at the top of the screen.
5	Select the next preset configuration from the list.
*	Generate a random configuration and animate until it stabilizes or dies. If it dies, generate a new random configuration.

The source code for this example can be found at:

`projects\Demo3D\src\com\superscape\m3g\wtksamples\life3d\Life3D.java`

The variable, `projects`, is the directory you are using to store your NetBeans projects.

RetainedMode

The `RetainedMode` MIDlet plays a scene file that shows a skateboarder in an endless loop. The source code is found at:

`projects\Demo3D\src\com\superscape\m3g\wtksamples\retainedmode`

PogoRoo

`PogoRoo` displays a kangaroo bouncing up and down on a pogo stick. To steer the kangaroo, use the arrow keys. Press up to go forward, down to go backward, and left and right to change direction. Try holding down the key to see an effect. The source code is found at:

`projects\Demo3D\src\com\superscape\m3g\wtksamples\pogoroo`

JSR 211: Content Handler API (CHAPI)

JSR 211 defines the Content Handler API (CHAPI). The basic concept is that MIDlets can be launched in response to incoming content (files). Modern mobile phones can receive content using SMS, infrared, Bluetooth, e-mail, and other methods. Most content has an associated content type. CHAPI specifies a system by which MIDlets can be launched in response to specific types of content.

See ["Using Content Handlers"](#) and ["Running the CHAPIDemo Content Browser."](#)


Using Content Handlers

In the Oracle Java ME SDK Content Handlers are integrated in a project as application descriptors. Content Handlers you define are packaged with the application

Follow these steps to work with content handlers in the CHAPIDemo sample application (see ["Running the CHAPIDemo Content Browser"](#)).

1. In the Projects window, right-click CHAPIDemo and select **Properties** from the context menu.
2. In the Category pane, select Application Descriptor, and click the Content Handlers tab.
3. In the Content Handlers table, each line in the list represents the settings for a content handler.

Figure 24–1 The Content Handlers Tab




- To create a new content handler, press **Add**, or to edit an existing content handler, press **Edit**. Both actions open the Content Handler Properties window. See ["Defining Content Handler Properties."](#)

- To adjust the order of the content handlers, select one and click **Move Up** and **Move Down**. To remove a content handler from the list, select it and press **Remove**.
- See [Defining Content Handler Properties](#) and ["Running the CHAPIDemo Content Browser."](#)

Defining Content Handler Properties

In the Projects window, right-click a project and select **Properties** from the context menu. In the Category pane, select Application Descriptor, and click the Content Handler tab. Pressing **Add** or **Edit** opens the Content Handler Properties window.

Figure 24–2 The Content Handlers Properties Window



- In the Class field, select a class name from the dropdown menu.
- ID is a required identification string when you invoke a content handler and control access.
- In Content types, list the content types for which this content handler is responsible. Use **Add Type** and **Remove** to manage the list.
- In Suffixes, provide a list of URL suffixes that act as a substitute for an explicit content type.


- In Access allowed to, list IDs for content handlers that are allowed access to this content handler. If the list is empty, access to this content handler is granted to every content handler.

Defining Content Handler Actions

Content handler actions give invoking applications a choice about how to handle content. An Action is associated with an existing content handler. An image viewer content handler, for example, might include an action for viewing the image at its original size and another action that makes the image fill the available screen space.

In the Projects window, right-click a project and select **Properties** from the context menu. In the Category pane, select Application Descriptor, and click the Content Handler tab. Press **Add** or **Edit** to open the Content Handler Properties window and click the Actions tab, as shown here.

Figure 24–3 *The Content Handlers Properties Window*



The Actions list contains the internal names of the actions for this content handler. Locales is a list of all the locales for which human-readable action names are provided. Localized Actions is a grid which contains the human-readable action names for various locales. Each locale is represented by a row, while the actions are listed as columns. You can see all the human-readable action names for a particular locale by reading across a single row.

Running the CHAPIDemo Content Browser

This demo is a content browser that takes advantage of the content handler registry. It enables you to view different types of content from different sources.

Note: For the demo to work this project must reside in the Oracle Java ME SDK installation's \apps subdirectory. You must create this directory yourself. For example,

1. Click the **File** menu and select **New Project**.
2. In the Categories window select **Samples > Java ME SDK 3.4** and single-click **CHAPIDemo**. Click **Next**.

Save the CHAPIDemo sample project in *installdir*\apps directory; for example, C:\Java_ME_platform_SDK_3.4\apps\CHAPIDemo. Click **Finish**.

3. Right-click the project and select **Properties**. Select the Running category, and select **Execute through OTA** and click **OK**.

Not all features of the demo are available if you select the Run command. Additionally, to see certain features of the demo, an HTTP server is required. The server is located in the *installdir*\apps directory. Also the audio and video files are located in the content directory, which must be located in the CHAPIDemo. directory (*installdir*\apps\CHAPIDemo\content).

You might see security messages as CHAPIDemo registers itself.

4. Launch CHAPIDemo.

On the Favorite Links page, select CHAPI Demo. Press **Select** or click the **Menu** soft button and select **Go**.

You might see a request for permission to use airtime. To speed up the demo interaction, select "Ask once per application use" and select the **Yes** soft key (if you do not check this option you can still use the demo but you see the airtime message more frequently).

The Text Viewer displays a Media Player URL and links to various media files.

5. Install the Media Player to view media.
 - Click the URL `http:handlers/dist/MediaHandler.jad`, or, use arrow keys to highlight the URL and from Menu, select **Go**.
 - The application asks, "Are you sure you want to install Media Handler?" Click the **Install** soft key.

An authorization Information screen is displayed.
 - Click the **Install** soft key.

The installation is confirmed and you are returned to the Text Viewer. The Media Handler shows as a separate application in the AMS.

6. Select and view the different image, video, audio and text URLs.

Click on a link to open that media in the viewer, or, use arrows to highlight the link, then select **Go** from the soft menu.

Select the **Back** soft key to return to the Text Viewer.

JSR 226: Scalable 2D Vector Graphics

JSR 226, Scalable 2D Vector Graphics for J2ME, supports rendering sophisticated and interactive 2D content.

Scalable Vector Graphics (SVG) is a standard defined by the World Wide Web Consortium. It is an XML grammar for describing rich, interactive 2D graphics.

The Scalable Vector Graphics (SVG) 1.1 specification (available at <http://www.w3.org/TR/SVG11/>) defines a language for describing two-dimensional graphics in XML.

SVG Tiny (SVGT) is a subset of SVG that is appropriate for small devices such as mobile phones. See <http://www.w3.org/TR/SVGMobile/>. SVGT is a compact, yet powerful, XML format for describing rich, interactive, and animated 2D content. Graphical elements can be logically grouped and identified by the SVG markup.

Java ME applications using SVG content can create graphical effects that adapt to the display resolution and form factor of the user's display.

SVG images can be animated in two ways. One is to use declarative animation, as illustrated in [Section , "Play SVG Animation."](#) The other is to repeatedly modify the SVG image parameters (such as color or position), through API calls.

While it is possible to produce SVG content with a text editor, most people prefer to use an authoring tool. Here are two possibilities:

- **Inkscape:** <http://inkscape.org>
- **Adobe Illustrator:**
<http://www.adobe.com/products/illustrator/main.html>

Running SVGDemo

This project contains MIDlets that demonstrate different ways to load manipulate, render, and play SVG content.

Click the **File** menu and select **New Project** and in the Categories window select **Samples** then select **Java ME SDK 3.4** and single-click SVGDemo. Click **Next**.

SVG Browser

The SVGBrowser MIDlet displays SVG files residing in the phone file system. Before running this demo, place an SVG file in your device skin's file structure. The default location is:

```
username\javame-sdk\3.4\work\devicename\appdb\filesystem\root1
```

For your device location, see ["Oracle Java ME SDK Directories"](#) and [Table 8–1](#). Launch the demo. The application displays the contents of `root1`. Select your SVG file and select the **Open** soft key.

Render SVG Image

Render SVG Image loads an SVG image from a file and renders it. Looking at the demo code you can see that the image is dynamically sized to exactly fit the display area. The output is clear and sharp.

Play SVG Animation

This application plays an SVG animation depicting a Halloween greeting card. Press 8 to pause, 5 to start or resume, and 0 to stop.

The SVG file contains a description of how the various image elements evolve over time to provide this short animation.

In the following code sample, the JSR 226 `javax.microedition.m2g.SVGImage` class is used to load the SVG resource. Then, the `javax.microedition.m2g.SVGAnimator` class can take all the complexity of SVG animations and provides a `java.awt.Component` or `javax.swing.JComponent` which plays the animation. The `SVGAnimator` class provides methods to play, pause, and stop the animation.

Example 25–1 SVG File Example

```
import javax.microedition.m2g.ScalableGraphics;
import javax.microedition.m2g.SVGImage;

...
String svgURI = ...;
SVGImage svgImage = (SVGImage) SVGImage.createImage(svgURI, null);
SVGAnimator svgAnimator = SVGAnimator.createAnimator(svgImage);

// If running a JSE applet, the target component is a JComponent.
JComponent svgAnimationComponent = (JComponent) svgAnimator.getTargetComponent();
...

svgAnimator.play();
...
svgAnimator.pause();
...
svgAnimator.stop();
```

Create SVG Image from Scratch

This demo builds an image using API calls. It creates an empty `SVGImage`, populates it with a graphical content, and then displays that content.

Bouncing Balls

Bouncing Balls plays an SVG animation. Press 8 to play, 5 to start, and 0 to stop. If you press 8, pressing 5 resumes the animation. If you press 0, pressing 5 starts the animation from the beginning.

Optimized Menu

In this demo, selected icons have a yellow border. As you move to a new icon, it becomes selected and the previous icon flips to the unselected state. If you navigate off the icon grid, selection loops around. That is, if the last icon in a row is selected, moving right selects the first icon in the same row.

This demo illustrates the flexibility that combining UI markup and Java offers: a rich set of functionality (graphics, animations, high-end 2D rendering) and flexibility in graphic manipulation, pre-rendering or playing.

In this example, a graphic artist delivered an SVG animation defining the transition state for the menu icons, from the unselected state to the selected state. The program renders each icon's animation sequence separately into off-screen buffers (for faster rendering later on), using the JSR 226 API.

With buffering, the MIDlet adapts to the device display resolution (because the graphics are defined in SVG format) and still retain the speed of bitmap rendering. In addition, the MIDlet is still leveraging the SVG animation capabilities.

The task of defining the look of the menu items and their animation effect (the job of the graphic artist and designer) is cleanly separated from the task of displaying the menu and starting actions based on menu selection (the job of the developer). The two can vary independently provided both the artist and the developer observe the SVG document structure conventions.

Picture Decorator

In this sample you use the phone keys to add decorations to a photograph. The key values are:

Key	Action
1	key shrink
2	key next picture
3	key grow
4	key help
5	key horizontal flip
6	key vertical flip
7	key rotate counter-clockwise
8	key previous picture
9	key rotate clockwise
#	display picker options

This demo provides 16 pictures for you to decorate.

Use the 2 and 8 keys to page forward and back through the photos.

To decorate, press # to display the picker. Use the arrow keys to highlight a graphic object. The highlighted object is enlarged. Press Select to select the current graphic or press the arrow keys to highlight a different graphic. Press Select again to add the graphic to the photo. When the decoration is added you see a red + on the graphic, indicating it is selected and can be moved, resized, and manipulated.

Figure 25-1 Adding a Graphic

Use the navigation arrows to move the graphic. Use 1 to shrink the graphic, and 3 to enlarge the graphic. Use 5 or 6 to flip, and 7 or 9 to rotate. When you are satisfied with the position, press Select. Look for a green triangle. This is a cursor. Use the navigation keys to move the green triangle around the picture. When the cursor is over an object it is highlighted with a red box. Press Select. The red + indicates the object is selected and it can be manipulated or removed.


Figure 25-2 Highlighting a Graphic

To remove a decoration (a property), select an object, then click the Menu soft key and select Remove prop.

Location Based Service

Launch the application. A splash screen (also used as the help) appears. The initial view is a map of your itinerary - a walk through San Francisco. The bay (in blue) is on the right of your screen. Press 1 to start following the itinerary. The application zooms in on your location on the map. Turn-by-turn directions appear in white boxes on the horizontal axis. While the itinerary is running, Press 7 to rotate the map counter-clockwise. Note, the map rotates and the text now appears on the vertical axis. Press 7 again to restore the default orientation. Press 4 to display the help screen.

Figure 25-3 A Location-Based Service Screen



Running SVGContactList

This application uses different skins to display the same contact list information and a news banner. The skins feature different colors and fonts.

Select SVGContactlist(skin 1) or SVGContactlist(skin 2), then click **Launch**.

Use the up and down arrows to navigate the list of contacts. The selected name is marked with a special character (a > or a dot) and is displayed in a larger font.

Press > or the select button to see more information for the selected name. When you are in the detailed view you can traverse the detail entries using the up or down arrows.

Press < or the select button to return to the contact list.

Press the left soft button to go back to the demos MIDlet list and view another skin.

JSR 239: Java Bindings for Open GL ES

JSR 239 provides a Java language interface to the open standard OpenGL ES graphics API.

OpenGL ES is a standard API for 3D graphics, a subset of OpenGL, which is pervasive on desktop computers.

Open GL Overview

JSR 239 defines the Java programming language bindings for two APIs, OpenGL for Embedded Systems (OpenGL ES) and EGL. EGL is a standard platform interface layer. Both OpenGL ES and EGL are developed by the Khronos Group
<http://khronos.org/opengles/>.

While JSR 184 (which is object oriented) requires high level functionality, OpenGL is a low-level graphics library that is suited for accessing hardware accelerated 3D graphics.

JSR 256: Mobile Sensor API Support

The JSR 256 Mobile Sensor API allows Java ME application developers to fetch data from sensors. A sensor is any measurement data source. JSR 256 supports many different types of sensor connections (wired, wireless, embedded, and more) but Oracle Java ME SDK only provides preconfigured support for sensors embedded in a device.

Sensors can vary from physical sensors such as magnetometers and accelerometers to virtual sensors that combine and manipulate the data they have received from various kinds of physical sensors. An example of a virtual sensor might be a level sensor indicating the remaining charge in a battery or a field intensity sensor that measures the reception level of the mobile network signal in a mobile phone.

The SDK GUI provides sensor simulation. The emulator's External Events Generator Sensors tab enables you to run a script that simulates sensor data.

You can use the API available with the SDK to create a custom sensor implementation with additional capabilities and support for different connection types.

The Sensors demonstration has two MIDlets, SensorBrowser and Marbles that demonstrate the SDK's implementation of the Mobile Sensor API.

Creating a Mobile Sensor Project

The Mobile Sensor API is automatically included in version 3.4 CLDC projects. In NetBeans, create a new Java ME Mobile Application, select the CLDC version 3.4 platform, and specify a device that supports CLDC-1.1 and MIDP-2.1 (JavaMEPhone1 for example).

A sensor project freely detects sensors, but this does not imply you can get data from the sensors you find. You might need to explicitly set permissions in your project so you can interact with certain sensors. To see an example, open the Sensors sample project. Right-click on Sensors and select Properties, select the Application Descriptor category, and select the API Permissions tab.

The following permissions work with the preconfigured embedded sensors shipped with the SDK:

- `javax.microedition.io.Connector.sensor`
Required to open a sensor connection and start measuring data.
- `javax.microedition.sensor.ProtectedSensor`
Required to access a protected sensor.
- `javax.microedition.sensor.PrivateSensor`

Required to access a private sensor.

A sensor is private or protected if the sensor's security property has the value `private` or `protected`. The security property is an example of a sensor property you might create for yourself in your own sensor configuration. You can create your own optional properties using `com.sun.javame.sensorN.proplist` and `com.sun.javame.sensorN.prop.any_name`, where *N* is the sensor number and *any_name* is the name of your property. The security sensor property was created as follows:

```
# add security into proplist
com.sun.javame.sensor<N>.proplist: security
# add security property value
com.sun.javame.sensor<N>.prop.security: private
```

Using a Mobile Sensor Project

The sample Sensor project can be installed over the air. To install the application into the emulator right-click the Sensors project and select **Properties**, select the Running category, select **Execute through OTA**, and click **OK**.

In the emulator window, click the **Tools** menus and select **External Events Generator**. In the External Events Generator, click the Sensors tab. In this tabbed pane, you can view all sensors currently available in the emulator, with the sensor ID, name, and availability. If the sensor supports change to availability you can click on the check box to change it. As mentioned earlier, the provided implementation does not support availability change, but a custom implementation you create might do so.

When you select a sensor row the bottom of the dialog displays any custom sensor controls. For example, the acceleration sensor, has three channels: `axis_x`, `axis_y`, and `axis_z`. Each channel has a slider that changes the current channel value, and an edit box you can use to input a value. The channel unit label is displayed on the far right.

Under the channels there is a script player control that enables you to play sensor value events from a script file of the format discussed in ["Creating a Sensor Script File."](#) See ["SensorBrowser"](#) for a description of how to use the Sensors demo.

Creating a Sensor Script File

To simulate sensor inputs, provide a sensor script. The file format is as follows:

Example 27–1 Sensor Script File Format Example

```
<sensors>
  <value time="0">
    <channel id="0" value="0" />
    <channel id="1" value="0" />
  </value>
  <value time="100">
    <sensor active="false"/>
  </value>
  <value time="100">
    <channel id="0" value="-50" />
    <channel id="1" value="10" />
    <sensor active="true"/>
  </value>
</sensors>
```

marbles.xml in the Sensors project directory is an example of a sensor script file. The attributes are as follows:

- The attribute time in the value tag is the delay from the previous command in milliseconds.
- The channel tag sets the value of the channel with the specified id value, to value. The channel ignores the id if the value of id is not specified or if the value is out of the channel range.
- The sensor tag is a true or false value that makes the sensor available or unavailable. The preconfigured sensors provided with this release are embedded, so they cannot be deactivated. If you configure your own sensor that is not embedded, it is possible to deactivate it.

SensorBrowser

The SensorBrowser application displays the sensor detail information for reach channel defined for the demo.

1. In the emulator, select SensorBrowser and use the soft key to select Launch the application.


Depending on your security settings you might see the warning: "Sensors" wants to connect to sensor <#>. Is it OK to use sensor? For test purposes, select "Ask once per application use" and select the **Yes** soft button.

The emulator displays a list of sensors.

2. Use the navigation keys to highlight a sensor, then use the soft key to select **Detail**.

For example, the following screen shows the details for the acceleration sensor.

Figure 27–1 Acceleration Sensor Screen



Click **Back**, then click **Exit** to return to the application menu.

Marbles

This demonstration uses the Marbles game to provide visual feedback for sensor inputs provided in a script.

1. From the application menu select Marbles and use the soft key to launch the application.
2. In the emulator, click the **Tools** menu and select **External Events Generator**. Click the Sensors tab to display a list of the sensors in this application.
3. Select the Acceleration Sensor row (ID 3).
4. Click the **Browse** button, and in the Sensors project directory select `marbles.xml`.
5. Observe the movement of the marbles on the emulator screen. On the external events screen you can see the sliders move as the script runs. You can use the familiar controls to play, pause, and stop the script.

JSR 257: Contactless Communication API

The Contactless Communication API (<http://jcp.org/en/jsr/detail?id=257>) is a Java ME optional package that allows applications to access information on contactless targets, such as Radio Frequency Identification (RFID) tags and bar codes. RFID tags are often used in business for item identification, article surveillance, and inventory. Each RFID tag contains a unique identification number used to identify a tagged object.

Using the JSR 257 API, an RFID reader can be built into an Oracle Java Wireless Client software phone stack, allowing the handset to read data from a tagged target and write data back to it. RFID readers use the 13.56 MHz radio frequency and the communication distance is usually less than 10 centimeters.

The Near Field Communication (NFC) Forum defines the NFC Data Exchange Format (NDEF) data packaging format. NDEF facilitates communication with an RFID tag, or between one NFC device and another. The Contactless Communication API provides a connection to any physical target that supports the NDEF standard, allowing applications to exchange data with any target tagged with NDEF formatting, regardless of actual physical type.

Using ContactlessDemo

The Oracle Java ME SDK provides a way to test contactless communication. The MIDlet running on the emulator waits to detect an RFID tag. You can simulate the tag communication using the emulator's external events generator to detect and attach the tag. You can use one of the tags included in the sample, or create tag files of your own, as described in "[Tag File Formats](#)."

1. Launch the ContactlessDemo. The MIDlet registers the RFID tag listener, the NDEF tag listener and the NDEF record listener, then notifies you that it is waiting for a tag.
2. In the emulator, click the **Tools** menu and select **External Events Generator**. The Contactless Communication tab is automatically displayed. In the external events generator, the tag emulator supplies several tags by default: `hello`, `nested`, `vcard`, `jdts`, `jdts2`, and `ndefEmpty`.
3. To test the connection, select an available tag and press the **Attach** tag.

In the emulator, the MIDlet notifies you that the NDEF target is detected, displays the tag information, and prints the payload if it is a text record.

In the external events generator, press **Detach tag** to end the session.

Events are recorded in the log area. To clear the log, right-click and select **Delete Text**. To clear the emulator screen press **Clear**.

4. To create your own tag, create a tag file according to the NDEF standard. For a sample, see ["Tag File Formats."](#)

In the External Events Generator, press **Create tag** and browse to select your tag file, and press **Open**. If the file is properly formed, the new tag is added to the available tags list. To write protect the tag, select the tag and select the **Locked** option. When a tag is locked, no data can be written to the tag.

Click **Remove tag** to remove any tag from the list. If it is a tag you created, the original file on disk is not affected. If the default tags are removed, they reappear when you restart the demo.

5. Optional. Instead of performing interactive actions in the external events generator, you can use a script to do the same thing.

Create a file as directed in ["Script Format."](#) In the external events generator, click the Browse button to locate your script, then press Play.

Tag File Formats

Tags are created in XML format in accordance with the NFC and NDEF standards. To see how the sample files are formed, see:

`install\dir\toolkit-lib\modules\emulator-ui-window-external-events\jsr257\conf\tags.`

A sample file with several records might look like this:

Example 28–1 Tag File Format Example

```
<?xml version="1.0" encoding="UTF-8"?>
<jsr257client>
  <UID>12-CD-45-67-89-AB-CD</UID>

  <TargetProperties>
    <TargetProperty>NDEF</TargetProperty>
  </TargetProperties>

  <NDEFMessage>
    <NDEFRecord>
      <Format>MIME</Format>
      <Name>text/plain</Name>
      <Id>mimeid</Id>
      <Payload>Hello, MIME World!</Payload>
    </NDEFRecord>
    <NDEFRecord>
      <Format>MIME</Format>
      <Name>text/example</Name>
      <Id>urn:company:product:ndef:payload:2</Id>
      <Payload>payload2</Payload>
    </NDEFRecord>
    <NDEFRecord>
      <Format>EXTERNAL_RTD</Format>
      <Name>urn:nfc:ext:oracle.com:type1</Name>
      <Id></Id>
      <Payload>payload3</Payload>
    </NDEFRecord>
    <NDEFRecord>
      <Format>URI</Format>
      <Name>urn:company:product:test_uri</Name>
      <Id>urn:company:product:ndef:payload:4</Id>
```

```

        <Payload>payload4/<Payload>
    </NDEFRecord>
    <NDEFRecord>
        <Format>NFC_FORUM_RTD</Format>
        <Name>urn:nfc:wkt:Sp</Name>
        <Id></Id>
        <Payload>smart-poster</Payload>
    </NDEFRecord>
    <NDEFRecord>
        <Format>MIME</Format>
        <Name>text/x-vCard</Name>
        <Id>duke</Id>
        <Payload>BEGIN:VCARD VERSION:2.1 FN:Oracle TEL:+1-650-506-7000
            ADR:500 Oracle Parkway City:Redwood Shores
            State:CA;94065 END:VCARD
        </Payload>
    </NDEFRecord>
</NDEFMessage>
</jsr257client>

```

Script Format

You can use the external events generator buttons to attach and detach a tag, or you can write a script to perform these actions. The script syntax is as follows:

Example 28–2 Tag Script File Format Example

```

# Comment:
#   # this is a comment
# Tag definition:
#   tag <tag name> <path to the tag xml file>
# Attach tag:
#   attach <tag name>
# Delay. Ensures the tag is attached before other actions.
#   wait <time in ms>
# Print tag information:
#   print <tag name>
# Detach tag:
#   detach <tag name>

```

This is a sample script:

Example 28–3 Tag Script Sample

```

tag C D:\MyTags\ccomtag.xml
attach C
print C
wait 10000
detach C

```

In the external events generator, click **Browse** and select the script file, then press Play to run the script. The results are shown in the Log area. For example, if the sample script calls the sample tag file in "[Tag File Formats](#)," the log output is as follows:

```

[18:24:10] Run Script: D:\JMESDKLocal\ccomtag.xml
[18:24:10] Define tag 2058 (C)
[18:24:10] Print 2058 (C)
[18:24:10] Attached tag 2058 (C)
[18:24:10] UID: 02-34-56-78-9A-BC-DE
Properties: NDEF

```

```
NDEF message: 8 record(s)
#0: NDEF record:  format=MIME, name=text/plain, id.length=2, payload.length=18
payload=Hello, MIME world!
#1: NDEF record:  format=MIME, name=text/example, id.length=34, payload.length=8
payload=payload2
#2: NDEF record:  format=EXTERNAL_RTD, name=oracle.com:type1, payload.length=8
payload=payload3
#3: NDEF record:  format=URI, name=urn:company:product:test_uri, id.length=34,
payload.length=8
payload=payload4
#4: NDEF record:  format=EXTERNAL_RTD, name=company.com:type1, id.length=34,
payload.length=8
payload=payload5
#5: NDEF record:  format=NFC_FORUM_RTD, name=Sp, payload.length=12
payload=smart-poster
#6: NDEF record:  format=URI, name=message/http, id.length=3, payload.length=56
payload=http://www.oracle.com/technetwork/java/javame/index.html
#7: NDEF record:  format=MIME, name=text/x-vCard, id.length=4, payload.length=122
payload=BEGIN:VCARD VERSION:2.1 FN:Oracle TEL:+1-650-506-7000
ADR:500 Oracle Parkway; City:Redwood Shores;State:CA;94065 END:VCARD
[18:24:10] Wait 10000ms
[18:24:20] Detached tag 2058 (C)
[18:24:20] Script finished.
[18:24:25] Received data for unknown tag 2,058
```

Installation and Runtime Security Guidelines

The Oracle Java ME SDK requires an execution model that makes certain networked resources available for emulator execution. These required resources might include - but are not limited to - a variety of communication capabilities between Oracle Java ME SDK components.

Note: the Oracle Java ME SDK installation and runtime system is fundamentally a developer system. It is not designed to guard against any malicious attacks from outside intruders.

During execution, the Oracle Java ME SDK architecture can present an insecure operating environment to the platform's installation file system, as well as its runtime environment. For this reason, it is critically important to observe the precautions outlined in these guidelines when installing and running the Oracle Java ME SDK.

Maintaining Optimum Network Security

To maintain optimum network security, Oracle Java ME SDK can be installed and run in a "closed" network operating environment, where the Oracle Java ME SDK system is not connected directly to the Internet. Or, it can be connected to a secure company Intranet environment that can reduce unwanted exposure to malicious intrusion.

An example of an Oracle Java ME SDK requirement for an Internet connection is when wireless functionality requires a connection to the Internet to support communications with the wireless network infrastructure that is part of a Java ME application execution process. Whether or not an Internet connection is required depends on the particular Java ME application running on Oracle Java ME SDK. For example, some Java ME applications can use an HTTP connection.

In any case, if the Oracle Java ME SDK is open to any network access you must observe the following precautions to protect valuable resources from malicious intrusion:

- Installing the Oracle Java ME SDK Demos plugin is optional. Some sample projects use network access and open ports. Because the sample code does not include protection against malicious intrusion, you must ensure your environment is secure if you select to install and run the sample projects.
- Install the Oracle Java ME SDK behind a secure firewall that strictly limits unauthorized network access to the Oracle Java ME SDK file system and services. Limit access privileges to those that are required for Oracle Java ME SDK usage while allowing all the bidirectional local network communications that are necessary for Oracle Java ME SDK functionality. The firewall configuration must

support these requirements to run the Oracle Java ME SDK while also addressing them from a security standpoint.

- Follow the principle of “least privilege” by assigning the minimum set of system access permissions required for installation and execution of the Oracle Java ME SDK.
- Do not store any data sensitive information on the same file system that is hosting the Oracle Java ME SDK.
- To maintain the maximum level of security, make sure the operating system patches are up-to-date on the Oracle Java ME SDK host machine.

Tips for Legacy Toolkit Users

If you previously used the Sun Java Wireless Toolkit for CLDC or the CDC Toolkit, the advice in ["Quick Start"](#) still applies. Although the user interface is quite different, the project concept is similar.

The following tips apply legacy terms and ideas to the SDK.

- Runtime focus is less on the project and more on device capabilities and the emulation process.

In legacy toolkits you had to be careful to match the platforms, the APIs, and the capability of the output device. The SDK handles this problem differently, but as described in ["Java ME Platforms,"](#) you should be sure that the emulator platform is correct and a device profile is selected.

Clicking the green arrow runs the main project. If no project is set as the main project, clicking the green arrow runs the current project. To set a main project, click the **Run** menu, select **Set Main Project**, and select a project from the dropdown menu. Alternatively, you can right-click any open project and select **run**.

In the device selector (**Tools > Java ME > Device Selector**) you can test many devices without changing the project properties. Right-click any device and select **Run Project**, **Run via OTA**, or **Run JAR or JAD...** and select a project, or in the case of running a JAR or JAD, select the application's JAR or JAD file. Only projects that are compatible with the device are shown in the context menu.

- Import applications from legacy toolkits to SDK projects. The installation of the legacy toolkit must exist on the host machine. See ["Import a Legacy MIDP Project,"](#) ["Create a Platform for Legacy CDC Projects,"](#) and ["Import a Legacy CDC Project."](#)
- Legacy toolkit **settings** are Application Descriptors in the SDK. Right-click a project and select **Properties**. Select the **Application Descriptor** category.
- Legacy toolkit **utilities** are generally accessible from **Tools > Java ME** submenu in the NetBeans IDE. For example, the WMA console, the Java ME SDK Update Center and more can be started from the **Tools > Java ME** submenu.

For example, select **Tools > Java ME > WMA Console** in the NetBeans IDE to see the WMA Console output.

- CPU Profiler, Network Monitor, and Memory Monitor utilities can be accessed from the **Profile** menu or by right-clicking a project and selecting **Profile**. See [Chapter 9, "Profiling Applications,"](#) [Chapter 10, "Network Monitoring,"](#) and [Chapter 11, "Monitoring Memory"](#) for information on running these utilities.
- The emulator is familiar, but there are some fundamental differences.

It is important to realize that the emulator is a remote process, and when it starts it is independent of the build process running in NetBeans. Stopping the build process or closing a project does not always affect the application running in the emulator. You must be sure to terminate the application from the emulator. For more on this topic, see ["Running a Project"](#) and ["Working With Projects."](#)

In the Wireless Toolkit, you could simultaneously run multiple versions of a device because the toolkit would increment the phone number automatically each time you launched a project. Because the emulator is now a remote process, the phone number is a unique property that must be set explicitly for the device instance.

The emulator has additional display functionality. See ["The CLDC Mobile Emulator."](#)