

Retek[®] Extract Transform and Load[™]

11.1

Programmer's Guide



The software described in this documentation is furnished under a license agreement and may be used only in accordance with the terms of the agreement.

No part of this documentation may be reproduced or transmitted in any form or by any means without the express written permission of Retek Inc., Retek on the Mall, 950 Nicollet Mall, Minneapolis, MN 55403.

Information in this documentation is subject to change without notice.

Retek provides product documentation in a read-only format to ensure content integrity. Retek Customer Support cannot support documentation that has been changed without Retek authorization.

Corporate Headquarters:

Retek Inc.
Retek on the Mall
950 Nicollet Mall
Minneapolis, MN 55403
888.61.RETEK (toll free US)
+1 612 587 5000

Retek[®] Extract Transform and Load (RETL)[™] is a trademark of Retek Inc.

Retek and the Retek logo are registered trademarks of Retek Inc.

This unpublished work is protected by confidentiality agreement, and by trade secret, copyright, and other laws. In the event of publication, the following notice shall apply:

©2003 Retek Inc. All rights reserved.

All other product names mentioned are trademarks or registered trademarks of their respective owners and should be treated as such.

Printed in the United States of America.

European Headquarters:

Retek
110 Wigmore Street
London
W1U 3RW
United Kingdom

Switchboard:
+44 (0)20 7563 4600

Sales Enquiries:
+44 (0)20 7563 46 46
Fax: +44 (0)20 7563 46 10



The Apache Software License, Version 1.1

Copyright (c) 2000 The Apache Software Foundation. All rights reserved. Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.

2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

3. The end-user documentation included with the redistribution, if any, must include the following acknowledgment:

"This product includes software developed by the Apache Software Foundation (<http://www.apache.org/>)." Alternately, this acknowledgment may appear in the software itself, if and wherever such third-party acknowledgments normally appear.

4. The names "Apache" and "Apache Software Foundation" must not be used to endorse or promote products derived from this software without prior written permission. For written permission, please contact apache@apache.org.

5. Products derived from this software may not be called "Apache", nor may "Apache" appear in their name, without prior written permission of the Apache Software Foundation.

THIS SOFTWARE IS PROVIDED "AS IS" AND ANY EXPRESSED OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE APACHE SOFTWARE FOUNDATION OR ITS CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

This software consists of voluntary contributions made by many individuals on behalf of the Apache Software Foundation. For more information on the Apache Software Foundation, please see <http://www.apache.org/>. Portions of this software are based upon public domain software originally written at the National Center for Supercomputing Applications, University of Illinois, Urbana-Champaign.

Customer Support

Customer Support hours:

Customer Support is available 7x24x365 via e-mail, phone and Web access.

Depending on the Support option chosen by a particular client (Standard, Plus, or Premium), the times that certain services are delivered may be restricted. Severity 1 (Critical) issues are addressed on a 7x24 basis and receive continuous attention until resolved, for all clients on active maintenance.

Contact Method Contact Information

Internet (ROCS) www.retek.com/support

Retek's secure client Web site to update and view issues

E-mail support@retек.com

Phone US & Canada: 1-800-61-RETEK (1-800-617-3835)
World: +1 612-587-5800
EMEA: 011 44 1223 703 444
Asia Pacific: 61 425 792 927

Mail Retek Customer Support
Retek on the Mall
950 Nicollet Mall
Minneapolis, MN 55403

When contacting Customer Support, please provide:

- Product version and program/module name.
- Functional and technical description of the problem (include business impact).
- Detailed step by step instructions to recreate.
- Exact error message received.
- Screen shots of each step you take.

Contents

Chapter 1 – Introduction.....	1
Enhancements of 11.x versions of RETL.....	2
Technical specifications	3
Data integration.....	3
Chapter 2 – Installation and system configuration	5
Installation.....	5
Upgrading from a 10.x release of RETL.....	6
Set up.....	7
The RETL Package Verification Tool (verify_retl)	8
Backwards Compatibility Notes.....	10
RFX Command line options.....	12
Configuration	15
Multi-byte character support	19
Chapter 3 – RETL interface	21
Schema file requirements	21
Schema file XML specification.....	22
Delimited record schema.....	24
Fixed length record schema.....	25
Configure RFX to print schema output in SchemaFile format	28
Chapter 4 – RETL program flow.....	29
Program flow overview	29
The general flow.....	30
A simple flow	31
A more complex flow.....	33
Online Help	34

Chapter 5 – Database operators	35
ORAREAD.....	35
ORAWRITE.....	35
DB2READ	35
DB2WRITE.....	35
TERAFERead.....	36
TERAWRITE.....	36
Read-write operators XML specification table	36
Tag usage examples	50
Chapter 6 – Input and output operators.....	53
DEBUG.....	53
NOOP	53
EXPORT	53
IMPORT.....	53
Input and output operators XML specification table.....	54
Tag usage examples	55
Chapter 7 – Join operators.....	57
INNERJOIN	57
LEFTOUTERJOIN	57
RIGHTOUTERJOIN.....	57
FULLOUTERJOIN.....	57
LOOKUP.....	58
Special notes about Join operators	58
Tag usage examples	61

Chapter 8 – Sort and merge operators.....	63
COLLECT and FUNNEL	63
SORTCOLLECT and SORTFUNNEL.....	63
HASH.....	63
SORT.....	63
MERGE.....	63
Sort and merge operators XML specification table	64
Tag usage examples	65
Chapter 9 – Mathematical operators	67
BINOP.....	67
GROUPBY.....	67
GROUPBY on multiple partitions	68
Mathematical operators XML specification table.....	69
Tag usage examples	70
Chapter 10 – Structures and data manipulation operators	73
CONVERT	73
FIELDMOD	75
FILTER	75
GENERATOR.....	76
REMOVEDUP	77
Structures and data manipulation operators XML specification table	77
Tag usage examples	80
Chapter 11 – Other operators.....	85
COMPARE.....	85
SWITCH.....	86
CHANGECAPTURE.....	87
COPY	88
DIFF	88
CLIPROWS.....	89
Other operators XML specification table.....	90
Tag usage examples	95

Appendix A – Default Conversions	97
Appendix B – Troubleshooting Guide.....	103
Appendix C – Database configuration and Troubleshooting Guide	111
RETL Database configuration and maintenance notes	111
Troubleshooting RETL with your database	111
Appendix D – FAQs.....	117
Appendix E – RETL 11.x-specific F.A.Qs	119

Chapter 1 – Introduction

RETL is a high performance, scalable, platform independent, and parallel processing data movement tool. RETL attempts to address several primary needs:

- Database independent applications.
- Platform independent applications.
- Developing such applications more quickly than possible with conventional coding methods (e.g. custom crafted C and/or C++ code).
- High performance data processing.

In order to provide for these needs, the RETL defines an interface (in XML) that applications can call to define ETL functions. This interface is in a well-defined XML form that allows access to any database that the RETL supports.

RETL is a cross-platform development tool supported on many different platforms (e.g. AIX, SunOS, and HP-UX). The XML definitions do not change on a per platform basis so moving between hardware platforms is a snap if you are using RETL.

Development of the XML instructions for RETL is much simpler, faster and less error prone than writing C and/or C++ code. The result is that applications can be completed much faster than possible with previous methods.

This guide shows you, the application developer, how to rapidly deploy RETL in your application and use it to manage your parallel processing system. Specifically, the guide provides information to:

- Install and set up RETL
- Configure RETL
- Administer RETL
- Develop applications using RETL

Select the RETL operators you need to perform your application's data processing tasks. Manage your system resources to scale your application by partitioning data across multiple processing nodes.

RETL resides as an executable on your application's platform, and on any other system that serves as a source or target of data.

The 11.x releases of RETL introduce a new high performance architecture written in Java.

Enhancements of 11.x versions of RETL

True Platform Independence – The new architecture of the 11.x releases has been written entirely in Java. As a result, RETL may now run on platforms that previously would have required significant efforts to port to. See the [FAQ question](#) related to platform independence and the Compatibility Matrix for supported platforms. As a direct result of the platform independence, significant RETL resources in platform maintenance will be freed up to develop new features going forward.

True Database Independence – With the 11.x releases, generic ‘dbread’/‘dbwrite’ operators have been introduced. These operators use JDBC-compliant technology to connect to databases in a truly database-independent manner. Additionally, previous 10.x releases were unable to connect to different database types in the same flow. 11.x releases allow full interoperability among different databases in the same flow (e.g. among db2, oracle, teradata all in the same flow). See the [FAQ question](#) related to database independence.

Improved performance – RETL 11.x releases include a new architecture that optimizes pipeline parallelism by consolidating connected operators into the same pipeline where possible. This reduces the number of threads required, minimizing context switching and thrashing among threads, and thereby allowing a framework that supports improved performance. Optimizations have been made in certain operators, namely oraread/orawrite and export, which have been shown to positively affect performance in comparison to 10.x releases. Internal performance benchmarking between 10.x and 11.x releases has shown 11.x releases to be anywhere from 15%-150% faster.

Error handling and debugging – 11.x releases introduce better flow debugging by giving line and column specific error messages when RETL encounters problems reading an XML flow definition. Additionally, 11.x’s exception handling allows for better error handling and debugging.

Online Help – A command-line option has been added to 11.x releases that allow flow developers to view operator syntax and usage via the command-line without having to refer to this document.

Simplified installation and configuration – 11.x releases consolidate code into a single binary rather than the 26 binaries of 10.x release. This considerably eases installation. In addition, there is less environment setup that needs to be done in order to complete an installation.

Backwards compatibility with previous releases – A requirement of 11.x versions is that they be backwardly-compatible with the 10.x versions. 11.x versions are stricter on enforcement of valid XML flow interfaces, input schemas, and data fields. In some instances, the 11.x product will find data and/or flow errors that may have previously been unreported. The result may be more discarded or rejected records and/or error messages than previously identified.

Technical specifications

RETL is certified on the platforms listed in this section. With the new architecture of 11.x releases of RETL, only one binary/runtime environment is necessary for all the supported platforms. For historical reasons the executable for RETL is called “rfx” and when referencing the executable we will use that name.

The release_notes.txt that documents the current configurations is included with the RETL CD. If you have a configuration that is not included in the release_notes.txt, verify with Retek Customer Support to see if your configuration is now available.

Supported Operating systems

Sun Solaris (version 8)

IBM AIX (versions 5.1. RETL 11.1 will not run on AIX 4.3.3)

HP-UX (versions 11 and 11i)

*See [“What if I want to run RETL 11.x on unsupported platforms?”](#)

Database management systems

Oracle (8i and 9i)

NCR TeraData (release 2 version 4.3)

*See [“What if I want to run RETL 11.x on unsupported databases?”](#)

Data integration

Integrate external data of these forms:

- Unix flat files
- RDBMS tables including Oracle and NCR TeraData

Chapter 2 – Installation and system configuration

Installation

Install RETL on each server system that will be involved in inputting, outputting, or processing data. For example, if one system outputs data files and another system inputs that data and processes it, install RETL on both systems.

- 1 Log in as the `root` user on the appropriate host.
- 2 Create Unix groups for the following environments:
 - `rfx` – group that owns the RETL software
- 3 Create a UNIX operating system account on the appropriate host, using `ksh` as the default shell. `rfx - rfx group`.
- 4 Create a directory where you will install this software.
- 5 Log in to the Unix server as `rfx`.
- 6 Mount the RETL CD on your UNIX server.
- 7 Change directories to the CD mount point `<cdrom_path>/<rfx_dir>`.
- 8 At a Unix prompt, enter: `>./install.sh`

Note: You must be in the `< cdrom_path>/<rfx_dir >` for the installation to successfully complete.

- 9 Follow the prompts to install RETL for your configuration.

```
$ ./install.sh
Enter directory for RETL software:
---> <enter path to RFX_HOME>
Is this the correct directory for the install? y or n
RFX_HOME: <path to RFX_HOME>
---> y
Creating RFX_HOME directory <path to RFX_HOME> ...
Creating install directory in <path to RFX_HOME> ...
Copying Library Files...
Copying Sample Files...
Copying Executables...
Copying Config File...
Copying JRE Files...
Installing The Java Runtime Environment (JRE) for
<platform>...
JRE installed successfully at <path to RFX_HOME>/JRE/HP-
UX/jre
Successful completion of RETL Install
```

To complete the RETL setup and installation:

1) Place the following in a .kshrc/ .profile to retain setup variables:

```
RFX_HOME=/release/pkg_mock/retl/test
```

```
PATH=/release/pkg_mock/retl/test/bin:$PATH
```

2) Be sure to verify any additional environment setup as per the "Setup" section

of the Programmers Guide.

3) Verify the installation by running the following command:

```
$RFX_HOME/bin/retl -version
```

```
$
```

- 10 Review the install.log file in the <base directory>/install to verify that RETL was installed successfully.
- 11 Set up your environment as per the Setup section below.
- 12 Verify the installation and setup by running the "verify_retl" script (see Testing the Setup (verify_retl)).

Upgrading from a 10.x release of RETL

11.x releases are required to be backwardly compatible with the XML flow interface of 10.x releases. As a result, minimal changes to a setup should be necessary to upgrade 10.x releases to 11.x releases. In short, these are the steps that you should follow:

- 1 Choose a new (and different) location to install the new version of RETL.
- 2 Install the new version of RETL following the installation instructions.
- 3 Change the environment that RETL runs within so that it refers to the new RFX_HOME (e.g. change within .kshrc or .cshrc).
- 4 Double check the environment variables to make sure that you weren't explicitly referring to old RFX directories explicitly.
- 5 Read the [Backwards Compatibility](#) section to determine the need to change flows/scripts.
- 6 Make any changes necessary to correct your flows to be able to run in 11.x versions.
- 7 Verify your flows/scripts run as expected. If any scripts/flows fail in running with the 11.x release but pass in running with the 10.x release and changes aren't otherwise noted in the [Backwards-compatibility notes](#), [FAQ](#), or RETL 11 Release Notes, notify support of this condition.

To make future upgrades more seamless, separate the RETL specific changes that you make to your environment so that the environment variables can be easily removed, modified and/or replaced when necessary.

Set up

- 1 After installation, set up your Unix environment for RETL. The following example shows the variables you need in your Unix profile to run RETL properly.

```
export RFX_HOME=<base directory>
export PATH=$RFX_HOME/lib:$RFX_HOME/bin:${PATH}
```

- 2 If you've selected an installation with database support, set up database and environment variables required for basic database setup. Please refer to the [Appendix C – Database Configuration and Troubleshooting Guide](#) for more information on setting up your database.

For Oracle:

```
export ORACLE_HOME=/your/Oracle_home/directory
export PATH=$ORACLE_HOME/bin:$PATH
```

For DB2:

```
. /your/DB2PATH/sql/lib/db2profile
export PATH=/your/DB2PATH/bin:$PATH
```

For TeraData*:

```
export PATH=/usr/odbc/lib:$PATH
```

For TeraData on AIX:

```
export LIBPATH=/usr/terajdbc/lib:$LIBPATH
```

For TeraData on HP-UX:

```
export SHLIB_PATH=/usr/terajdbc/lib:$SHLIB_PATH
```

For TeraData on Solaris:

```
export
LD_LIBRARY_PATH=/usr/terajdbc/lib:$LD_LIBRARY_PATH
```

Note: Installation on teradata requires the Teradata JDBC utilities installed to /usr/terajdbc. Also, /usr/terajdbc/classes/teradata.jar should be copied to \$RFX_HOME/lib prior to running RETL.

- 3 Log in to the Unix server as rfx. At the Unix prompt, enter:


```
>rfx
```
- 4 Make any changes to rfx.conf defaults. For example, oracle database operators require hostname/port to be specified. These changes may be made to rfx.conf as DEFAULTS for convenience. See the [example rfx.conf](#) for details
- 5 If RFX is installed correctly and the .profile is correct, the following results:


```
rfx: Error : Flow file argument ('-f') required!
```

Note: See the Troubleshooting section at the end of this document if you have problems or issues.

The RETL Package Verification Tool (verify_retl)

When setting up RETL in a new environment (or if you'd just like to verify that the RETL environment is set up properly) run the "verify_retl" script located in the /bin directory of the RETL installation (note verify_retl is available as of release 10.2).

Note: RFX_HOME should be set properly prior to running verify_retl.

The RETL package verification tool performs the following checks:

- 1 Verifies environment variables/etc is set up properly.
- 2 Ensures that the RETL binary is installed properly and can run.
- 3 Runs a series of system tests derived from the samples directory.
- 4 Logs information about environment setup in a log file.

The usage for verify_retl is as follows:

```
verify_retl [-doracle] [-ddb2] [-dtera] [-nodb] [-h]
```

Option	Description
-doracle	Checks environment variables etc, for the Oracle installation of RETL.
-ddb2	Checks environment variables etc, for the DB2 installation of RETL.
-dtera	Checks environment variables etc, for the TeraData installation of RETL.
-nodb	Checks environment variables for the standalone version of RETL.
-h	Displays the help message.

This generates the following output if successful:

```
Checking RETL Environment...found ORACLE
environment...passed!
Checking RETL binary...passed!
Running samples...passed!
=====
=====
Congratulations! Your RETL environment and installation
passed all tests. See the programmer's guide for more
information about how to further test your database
installation (if applicable)
=====
=====

Exiting...saving output in /files0/retl/tmp/verifyretl-
20384.log
```

Check the “RETL ENVIRONMENT SETUP” section of the log file for important information on environment variables that must be set.

Backwards Compatibility Notes

A major requirement for RETL 11.x releases is that they be backwardly compatible in the XML interface with 10.3.x releases. Much effort has been expended to provide this compatibility; however, there are a few small changes that must be made for certain operators when upgrading to 11.x from 10.x releases of RETL.

XML flow interface/operator differences between 10.x and 11.x releases:

Operator	Property	Backwards Compatibility Notes
Filter	filter	<p>DEPRECATED SYNTAX – Previous (10.x) versions produced warning messages to correct ‘filter’ syntax. 11.x will not accept the following syntax in the filter property : >, <, >=, <=, =. These operations are replaced by GT, LT, GE, LE, EQ, respectively.</p>
Database read operators (oraread, db2read, teraferead)	query	<p>INVALID SYNTAX – Previous (10.x) versions allowed input of invalid XML in the query property of the dbread operators. Characters such as ‘>’ and ‘<’ in the query property will cause 11.x versions to produce an error message.</p> <p>An example follows:</p> <p>Previous XML valid in 10.x versions:</p> <pre><PROPERTY name="query" value="SELECT * FROM ANY_TABLE WHERE ANY_COLUMN > 1" /></pre> <p>Property should now appear as the following in 11.x versions:</p> <pre><PROPERTY name="query"> <![CDATA[SELECT * FROM ANY_TABLE WHERE ANY_COLUMN > 1]]> </PROPERTY></pre> <p>Note: A script has been provided to modify any flows to conform to the XML standard. This script is located in \$RFX_HOME/bin/fix_flow_xml.ksh. View the header of the script for usage information.</p>
Database read/write operators (oraread/orawrite, db2read/db2write, teraferead/terawrite)	dbname	<p>NEW REQUIRED PROPERTY – The database to connect to. This property should be used instead of ‘sid’ going forward.</p>
	port	<p>NEW REQUIRED PROPERTY – The port on which the database listener resides.</p> <p>Note: For Oracle databases, use tnsping to obtain the port number. The default for Oracle is 1521.</p> <p>Note: this may need to be specified only once in the rfx.conf configuration file for convenience.</p>

Operator	Property	Backwards Compatibility Notes
	hostname	<p>NEW OPTIONAL PROPERTY – The fully specified hostname or IP address where the database resides.</p> <p>Note: This property should only be specified when it is known that connections are being made to a remote database</p> <p>Note: this may need to be specified only once in the rfx.conf configuration file for convenience.</p>

Example (in operator):

```
<OPERATOR type="orawrite">
  <OUTPUT name="test.v" />
    <PROPERTY name="dbname"
value="databasename" />
    <PROPERTY name="connectstring"
value="userid/password" />
    <PROPERTY name="tablename" value="mytable" />
    <PROPERTY name="createtablemode"
value="recreate" />
    <PROPERTY name="hostname"
value="myhostname" />
    <PROPERTY name="port" value="1521" />
</OPERATOR>
```

Example (in rfx.conf):

```
<DEFAULTS operator="orawrite">
  <PROPERTY name="hostname"
value="myhostname" />
  <PROPERTY name="port" value="1521" />
</OPERATOR>
```

Feature Support differences between 10.x and 11.x releases

RETL 11.x does not fully implement certain command-line arguments and will not accept long argument options (e.g. -flow-file instead of -f)

Hardware requirements differences between 10.x and 11.x versions

- In general, more physical memory is required in order to run the 11.x versions of RETL. There is no general formula or guideline for the additional memory requirement since it strongly correlates to the flow, data, configuration, etc.

RFX Command line options

You can get help on rfx options on the command line by typing “rfx -h” on the command line. You should see something like the following:

```
>rfx -h
rfx [ OPTIONS ]

-h                Print help and exit
-oOPNAME         Print operator help. Valid values:
                  operator name or 'ALL' for all ops
-e              Print RETL environment variable usage
-v              Print version and exit
-cFILE          Configuration File
-nNUMPARTS      Number of Partitions (SMP only)
-x              Disable partitioning (default=off)
-sTYPE          Display schema as TYPE. Valid values:
                  NONE,SCHEMAFILE (default=NONE)
-lLOGFILE       Log statistics/times to LOGFILE
-fFLOWFILE      XML file containing flow
-d              Produce daVinci files (default=off)
-g              Produce GraphViz files (default=off)
```

These options are discussed in more detail in the table below:

Option	Default Value	Description
-h	n/a	Shows the help message shown above.
-oOPNAME	n/a	Displays syntax usage for operator specified in OPNAME, or for all operators if OPNAME is 'ALL'. Valid operator names are the same as those operators used in the XML flow interfaces. The intention with this option is to provide 'online syntax help' for flow developers, reducing the need to refer to this document for syntax usage. See the Online Help section for more information about this option.
-V	n/a	Displays the version and build number.
-cSTRING	\$RFX_HOME/ etc/rfx.conf	Overrides the default configuration file.
-nINT	As specified in the rfx.conf – or 1 if no rfx.conf is found.	The number of partitions to use. This feature is intended for RETL experts only.
-x	Partitioning as defined in the rfx.conf.	Disables partitioning.
-sTYPE	NONE	Prints the input and output schemas for each operator. Valid values and descriptions: NONE – rfx will not print any schema information. SCHEMAFILE – if specified, This option prints the input and output for each operator in schema file format so that developers can quickly and easily cut and paste rfx output to a file and break up flows. Developers could then modify these files for the purposes of specifying IMPORT and EXPORT schema files. Note: rfx should be run with the –sNONE option in production systems where unnecessary output is not needed. The –sSCHEMAFILE option is often useful in development environments where it is desirable to debug rfx flows by breaking them up into smaller portions.

Option	Default Value	Description
-ILOGFILE	n/a	Specifies the logfile in which to log rfx statistics/times. If the logfile path is relative, the log file will be placed in the directory as defined in the TEMPDIR element of the rfx configuration file (rfx.conf). This changes the default log file as specified in rfx.conf and will turn on logging only if the log level in rfx.conf is 'on'. For more information about the LOGGER feature, see the next section, entitled "Configuration"
-fSTRING	n/a	Specifies the file to use as input to rfx. This is where the XML flow is located. If no file is specified, rfx will read from standard input. The following is the syntax to use when reading from stdin via the korn shell (ksh): <pre>rfx -f - <<EOF <FLOW> ... </FLOW> EOF</pre>
--davinci-files	Off	This option is not currently supported.
--graphviz-files	Off	This option is not currently supported for 11.x versions.

Configuration

A configuration file may be specified by a user to control how rfx uses system resources, where to store temporary files, and to set default values for operators.

Configuration field descriptions

These explanations should assist you in modifying your configuration file. The RETL configuration file, rfx.conf, is located in the <base_directory>/etc directory.

Element Type	Attribute Name	Attribute Value	Description
CONFIGURATION			The root element of the RFX Configuration file. This element can have either NODE or DEFAULTS elements.
NODE	Hostname	Host name	The name of the UNIX server where RETL is installed.
	Bufsize	8..n	The number of records allowed between operators at any given time. The default bufsize is 2048 records. The bufsize can have a significant impact on performance. Setting this value too low causes a significant amount of contention between processes – slowing down RETL. A value that is too high can also slow RETL down because it will consume more memory than it needs to. Finding the right value for your hardware configuration and flow is part of tuning with RETL.
	Numpartitions	1..n	Optional value, defaults to 1.

Element Type	Attribute Name	Attribute Value	Description
TEMPDIR	Path	Valid path	<p>TEMPDIR is a child element of the NODE Element. It is the path to the directory where the RETL writes temporary files. We recommend that the number of temporary directories equals the number of partitions in order to maximize performance. Ideally each temp directory should be on a separate disk controller.</p> <p>Note: These directories must always be local to the host where rfx is running. Use of network drives can have a drastic impact on performance.</p> <p>Note: Care should be taken to protect the files within this directory since they can sometimes contain userid and password information. Please talk to your system administrator about setting the permissions so that only the appropriate personnel can access these files (e.g. by setting: umask 077).</p> <p>Note: Temporary files should be removed from temporary directories on a daily or weekly basis. This very important server maintenance task aids in RETL debugging, reviewing database-loading utility log files, and so on. If a RETL module fails, the user should not re-run the module before removing the temporary files that were generated by the failing module.</p>
GLOBAL			This element specifies global options for global settings within RFX.
	bytes_per_character	1,2, or 3	This setting specifies how RFX treats character data. In short, it affects how many bytes are in a character and can be used to allow RFX to work seamlessly with UNICODE data.
LOGGER			The LOGGER element specifies a facility for rfx to log information to. This gives a dynamic view of RETL to allow developers to get some information about the data that flows through each operator. This also enables developers to determine if/when deadlock conditions occur, debug problems and tune performance. See the properties that follow on how to configure the LOGGER for rfx.
	Type	file	The type of logging facility to use. Currently the only value rfx allows is to log to a 'file'.

Element Type	Attribute Name	Attribute Value	Description
	Dest	<output filename>	An optional output destination to log to. Currently, this value must be an absolute or relative filename. If the filename is relative, the log file will be placed in the directory as defined in the TEMPDIR element of the rfx configuration file (rfx.conf). The log file can be overridden by specifying -ILOGFILE as a command-line parameter to rfx. The default value is "rfx.log".
	level	0,1,2	<p>Specifies the level of detailed information recorded in the log file. Higher levels mean more information is logged.</p> <p>The following characteristics can be recorded:</p> <ul style="list-style-type: none"> • rfx start and stop time along with command line parameters. • The flow name – if specified as part of the flow. • Statistics per operator – start time, stop time, record counts and records per second per operator. <p>loglevel values have the following meaning: "0" = no logging. "1" = logging of a and b above. "2" = logging of a, b and c above.</p> <p>Note: leave logging turned off in production systems where performance is a critical factor. The logging feature is not designed to log errors, but is intended to give rough measures of flow performance characteristics and aid in debugging flows. It is recommended to periodically remove the log file to free unneeded disk space.</p>
DEFAULTS			<p>This element is a child of CONFIGURATION element.</p> <p>This section is used to define one or more default PROPERTY values for operators that are reused frequently. Care should be taken when using and changing these defaults since they can change the results of an rfx flow without changing individual flows.</p>
	operator		Name of the operator to assign default values. Refer to the following chapters for the operators that are available.
PROPERTY			This element is a child of the DEFAULTS element.

Element Type	Attribute Name	Attribute Value	Description
	name		The name of the operator property to assign a default value. Refer to Chapter 5 for the property names for each operator.
	value		The value assigned as the default for the specified operator property. Refer to Chapter 5 for valid property values for each operator.

The following is a sample resource configuration for RETL:

```

<CONFIG>
  <NODE      hostname="localhost"
            numpartitions="1"
            bufsize="2048" >
    <TEMPDIR path="/u00/rfx/tmp"/>
    <TEMPDIR path="/u01/rfx/tmp"/>
  </NODE>
  <GLOBAL   bytes_per_character="1" >
    <LOGGER  type="file"
            dest="rfx.log"
            level="0" />
  </GLOBAL>
  <DEFAULTS operator="oraread">
    <PROPERTY name="maxdescriptors" value="100"/>
    <PROPERTY name="hostname" value="mspdev25"/>
    <PROPERTY name="port" value="1521"/>
  </DEFAULTS>
  <DEFAULTS operator="orawrite">
    <PROPERTY name="hostname" value="mspdev25"/>
    <PROPERTY name="port" value="1521"/>
  </DEFAULTS>
</CONFIG>

```

Multi-byte character support

The optional variable “bytes_per_character” allows RETL to provide multi-byte character support. The number of bytes read or written is dependent upon the size of a character. RETL determines the size of a string by multiplying the number of characters by bytes_per_character. If you are using databases, bytes_per_character is set up by consulting your database configuration.

For Imports and Exports, RETL uses the schema file to determine the number of bytes a particular string will have. For a fixed length field the number of bytes is simply <number of chars> * <bytes_per_character>. For delimited fields, the maximum number of bytes is <maxlength>*<bytes_per_character>.

Chapter 3 – RETL interface

RETL can process datasets either directly from a database or from file-based systems. Depending upon the data source, one of two operators can perform this function. For reading data directly from database tables, use the DBREAD operators—ORAREAD, DB2READ, or TERAREAD—for the database. See Chapter 5 - Database operators, for more information about how to use each DBREAD operator. For situations where you expect RETL to process data in a file format, use the IMPORT operator. This operator imports a disk file into RETL, translating the data file into a RETL dataset.

Note: We use DBREAD and DBWRITE throughout this guide as shorthand to indicate any one of the database read or write operators as detailed in Chapter 5 - Database operators.

Schema file requirements

RETL stores information about each dataset that describes the data structures (the metadata). The means by which you supply metadata is dependent on whether you interface data using the DBREAD or IMPORT operator. When datasets are created using DBREAD, the metadata is read along with the data directly from the database table. In this case, RETL requires no further metadata. On the other hand, if the IMPORT operator is used for dataset input, RETL requires the use of a schema.

The schema ensures that datasets are consistent from the source data to the target data. RETL reads in a schema file that is specific to the dataset that is being imported. RETL uses the schema file to validate the input dataset structure. For example, if the dataset ultimately populates a target table in a database, the schema file dictates the type and order of the data, as well as the data characteristics, such as the character type, length, and nullability.

Two types of schema files are defined for use with an incoming text data file:

- Delimited file type
- Fixed length file type

Schema file XML specification

Element Type	Attribute Name	Attribute Value	Description
RECORD			The root element.
	type	“delimited” or “fixed”	Describes whether the schema is fixed records or delimited records.
	final_delimiter	character	Required field. End of record delimiter that is used within the input file to distinguish the end of a record. This is extremely important to help distinguish between records in the event that the input datafile is corrupt. Generally this is a newline character for readability.
	len	1..n	Required only for fixed length fields. This is the total length of the fixed length record. Note that this must be equivalent to the sum of all aggregate field lengths.
	Sortkeys	<space separated list of keys >	Optional property to specify the space-separated keys that the records are presorted by. This should be used only when it is known that the records will always be sorted by specified keys and it is necessary to remove the sort for performance purposes. This property must be specified in conjunction with ‘sortorder’.
	sortorder	asc or desc	Optional property to specify the sort order of the record. Specify ‘asc’ for ascending sorted order and ‘desc’ for descending sorted order. This should be used only when it is known that the records will always be sorted by specified keys and it is necessary to remove the sort for performance purposes. This must be specified in conjunction with ‘sortkeys’.
FIELD			Child element of the RECORD.
	name		The column name of the given field.
	delimiter		This optional attribute is for delimited fields only. It specifies the end of field delimiter, which can be any character, but the default value is the pipe character (‘ ’).

Element Type	Attribute Name	Attribute Value	Description
	datatype	Any one of: “int8”, “int16”, “int32”, “int64”, “uint8”, “uint16”, “uint32”, “uint64”, “dfloat”, “sfloat”, “string”, “date”, “time”, or “timestamp”	The datatype of the field. If the date data type is declared, the incoming data must be formatted as ‘YYYYMMDD’. If the time data type is declared, the incoming data must be formatted as ‘HH24MISS’. If the timestamp data type is declared, the incoming data must be formatted as ‘YYYYMMDDHH24MISS’
	nullable	“true” or “false”	Optional field describing whether null values are allowed in the field. The default value is false. If true then a nullvalue MUST be specified.
	nullvalue	Quoted string	Required if nullable=“true”. This is the text string that an IMPORT operator looks at to determine whether or not a field is null when reading flat files. This should be a unique value that will not otherwise be found within the dataset. For fixed length fields, this value must be equal in length to the field length so that the record length remains fixed. Note: The null string may specified (“”) for a fixed length field rather than specifying a number of blanks equivalent to the length of the field. Note: Null values must be a valid value for the type specified. For example, ‘00000000’ as a nullvalue for a date is invalid.
	maxlength	Number	Required only for delimited “string” fields. Specifies the maximum allowable length of the string field.
	len	Number	Required only for all fixed length fields. Specifies the length of the field.
	strip	“leading”, “trailing”, “both”, or “none”	Optional attribute used for delimited “string” fields to determine whether and how white space (tabs and spaces) should be stripped from input field. The default value is “none”. Note: this is not currently implemented for RETL 11.x.

Delimited record schema

When you create a schema for use with a delimited file type, follow these guidelines:

- The delimiter can be any symbol.

Note: Make sure the delimiter is never part of your data.

- To define the field's nullability, set **nullable** to 'true' or 'false'.
- If the field is nullable, set the default **nullvalue**. This is often set to "" – the null string.
- For the **string** data type, specify the **maxlength**.

An example delimited schema file

```
<RECORD type="delimited" final_delimiter="0x0A">
<FIELD name="colname1" delimiter="|" datatype="int8"
nullable="false"/>
<FIELD name="colname2" delimiter="|" datatype="int16"
nullable="true"
nullvalue=""/>
<FIELD name="colname3" delimiter="|" datatype="int32"
nullable="true" nullvalue=""/>
<FIELD name="colname4" delimiter="|" datatype="int64"
nullable="true" nullvalue=""/>
<FIELD name="colname5" delimiter="|" datatype="dfloat"
nullable="true" nullvalue=""/>
<FIELD name="colname6" delimiter="|" datatype="string"
maxlength="5" nullable="false"/>
<FIELD name="colname7" delimiter="|" datatype="date"
nullable="false"/>
<FIELD name="colname7" delimiter="|"
datatype="timestamp" nullable="false"/>
<FIELD name="colname8" delimiter="|" datatype="uint8"
nullable="false"/>
<FIELD name="colname9" delimiter="|" datatype="uint16"
nullable="true" nullvalue=""/>
<FIELD name="colname10" delimiter="|" datatype="uint32"
nullable="true" nullvalue=""/>
<FIELD name="colname11" delimiter="|" datatype="uint64"
nullable="true" nullvalue=""/>
<FIELD name="colname12" delimiter="|" datatype="sfloat"
nullable="true" nullvalue=""/>
</RECORD>
```

Fixed length record schema

When you create a schema for use with fixed length records, follow these guidelines:

- Specify the length (“len”) of the record.
- Specify a “len” value for every field. The total of all fields must be equivalent to the record length.
- To define the field’s nullability, set `nullable` to “true” or “false”.
- If the field is nullable, set the default `nullvalue`. Remember that since this is a fixed length field the null value must be the correct length for the field.
- If possible, specify the “final_delimiter” to ensure that input files are at least record-delimited so that RETL can recover in the event that data is corrupted or invalid.

Note: Make sure the `final_delimiter` is never part of your data.

An example fixed length schema file

```
<RECORD type="fixed" len="99" final_delimiter="0x0A">
<FIELD name="colname1" len="2" datatype="int8"
nullable="false"/>
<FIELD name="colname2" len="5" datatype="int16"
nullable="false"/>
<FIELD name="colname3" len="10" datatype="int32"
nullable="false"/>
<FIELD name="colname4" len="18" datatype="int64"
nullable="false"/>
<FIELD name="colname5" len="6" datatype="dfloat"
nullable="true" nullvalue="NULVAL"/>
<FIELD name="colname6" len="5" datatype="string"
nullable="false"/>
<FIELD name="colname7" len="8" datatype="date"
nullable="false" />
<FIELD name="colname7" len="14" datatype="timestamp"
nullable="false"/>
<FIELD name="colname8" len="2" datatype="uint8"
nullable="false"/>
<FIELD name="colname9" len="4" datatype="uint16"
nullable="true" nullvalue="XXXX"/>
<FIELD name="colname10" len="5" datatype="uint32"
nullable="true" nullvalue=" " />
<FIELD name="colname11" len="18" datatype="uint64"
nullable="false"/>
<FIELD name="colname12" len="18" datatype="sfloat"
nullable="false"/>
</RECORD>
```

Consider carefully your nullvalue.

Because nullvalues can be changed between import and export schemas, it is possible to lose data if you are not careful. However, this property can also be used to assign default values to null fields on export. No matter how you use them, care should be taken when selecting values for a field's nullvalue. Unless you are assigning a default value to a null field on export we strongly recommend against using a value that can actually appear as a valid value within a given dataset.

To illustrate consider the following schema (named "1.schema"):

```
<RECORD type="delimited" final_delimiter="0x0A">
  <FIELD name="colname1" delimiter="|"
  datatype="int8" nullable="false" />
  <FIELD name="colname2" delimiter="|"
  datatype="dfloat" nullable="true" nullvalue="" />
</RECORD>
```

Also consider this schema (named "2.schema") where the nullvalue has been modified for the second field:

```
<RECORD type="delimited" final_delimiter="0x0A">
  <FIELD name="colname1" delimiter="|"
  datatype="int8" nullable="false" />
  <FIELD name="colname2" delimiter="|"
  datatype="dfloat" nullable="true" nullvalue="0.000000" />
</RECORD>
```

When running through the following flow:

```
<FLOW>
  <OPERATOR type="import">
    <PROPERTY name="inputfile" value="1.dat" />
    <PROPERTY name="schemafile" value="1.schema" />
    <OUTPUT name="import.v" />
  </OPERATOR>
  <OPERATOR type="export">
    <INPUT name="import.v" />
    <PROPERTY name="outputfile" value="2.dat" />
    <PROPERTY name="schemafile" value="2.schema" />
  </OPERATOR>
</FLOW>
```

Where 1.dat contains the following data:

```
2|
3|4.000000
4|5.000000
5|0.000000
```

The following is the resulting output to 2.dat:

```
2|0.000000
3|4.000000
4|5.000000
5|0.000000
```

By using an export schema that has valid values to represent the nullvalue for the second field, this flow has assigned a default value to all of the second field's null values.

Then, if you change the input and schema files as in the following flow:

```
<FLOW>
  <OPERATOR type="import">
    <PROPERTY name="inputfile" value="2.dat" />
    <PROPERTY name="schemafile" value="2.schema" />
    <OUTPUT name="import.v" />
  </OPERATOR>
  <OPERATOR type="export">
    <INPUT name="import.v" />
    <PROPERTY name="outputfile" value="3.dat" />
    <PROPERTY name="schemafile" value="1.schema" />
  </OPERATOR>
</FLOW>
```

3.dat will look like this:

```
2|
3|4.000000
4|5.000000
```

5|

Note: Null values are always considered the smallest value in a field. That is, for any value n, null < n. In sorted order terms, null values come first (precede) in ascending and come last (follow) in descending order.

Configure RFX to print schema output in SchemaFile format

One error prone area in the development of RFX is when developers break up and put together flows. The interface between flows is the schema files that tell RFX how to read/write files. Writing schema files manually is tedious and error prone. We highly recommend that developers use the '-sSCHEMAFILE' command line option to speed up development. For more information about this feature, see the section [RFX Command line options](#).

Chapter 4 – RETL program flow

Program flow overview

The following text and diagram provides an overview of the RETL input-process-output model. The data input operators to RETL processing include the following:

- DBREAD, where data is read directly from a database
- IMPORT, where RETL accepts a data file
- GENERATOR, where RETL itself creates data input


Data process operators commonly include those that transform data in the dataset being processed, including:

- GROUPBY, which can be used to sum values in a table column

The data output process can include the use of the following operators:

- DBWRITE, where RETL writes data directly to the database
- DEBUG, which can be used to print records directly to the screen (stdout).
- EXPORT, which can export data to a flat file

The general flow




The diagram above is a general representation of the form that all flows take. Every flow must have a Data Input (or Source) and a Data Output (or Sink). These flows may optionally perform transformations on the input data before sending it to the Data Output.

Some things to note about all flows:

- When an operator generates an output dataset, that output dataset must be input into another operator. The data “flows” from one operator to another along the datasets (the arrows between the operators above).
- DATA INPUT operators have no dataset inputs – they get data from outside sources (e.g. Oracle database, DB2 database, TeraData database or flat file).
- Similarly, DATA OUTPUT operators are terminal points within the flow. They do not generate output datasets – rather they export records to an external repository (for example, Oracle, DB2, TeraData databases, or flat files).

In the next several sections we look at specific flows.

A simple flow



The diagram above is one way to represent a simple flow. This flow contains three operators: ORAREAD, FIELDMOD and EXPORT. This flow also contains two datasets – these are the simple arrows that connect the operator boxes above. The arrow from ORAREAD to FIELDMOD means that records flow from the ORAREAD operator to the FIELDMOD. Likewise the arrow from FIELDMOD to EXPORT indicates that the records from the FIELDMOD are passed onto the EXPORT operator.

In this flow diagram, several attributes are also shown to give us more information about what exactly this flow does. This flow pulls the “COMPHEAD” table out of the “ORA_SID” database (via the ORAREAD operator), renames the column “CMPY_IDNT” to “COMPANY” (via the FIELDMOD operator), and exports the resulting records to the file “results.txt” (via the EXPORT operator).

Here is XML for the above flow:


```

    <FLOW name="cmpy.flw">
<OPERATOR type="oraread">
  <PROPERTY name="dbname" value="ORA_SID"/>
  <PROPERTY name="connectstring" value="userid/passwd"/>
  <PROPERTY name="query">
    <![CDATA[
select * from COMPHEAD
]]>
  </PROPERTY>
  <OUTPUT name = "data.v"/>
</OPERATOR>
<!-- This is the format for a comment.
  -- They can of course be
  
```

```
-- multi-line, but cannot be nested.
-->
<OPERATOR type="fieldmod">
  <PROPERTY name="rename" value="CMPY_IDNT=COMPANY"/>
  <INPUT    name = "data.v"/>
  <OUTPUT   name = "comphead.v"/>
</OPERATOR>
<OPERATOR type="export">
  <INPUT    name="comphead.v"/>
  <PROPERTY name="outputfile" value="results.txt"/>
</OPERATOR>
</FLOW>
```

A more complex flow

Flows can get much more complex than the simple flow shown above.



The above flow pulls in data simultaneously from a flat file and Oracle Database. The dataset from the file is filtered based upon the specified filter criterion then sorted. In parallel, the dataset from the Oracle database is modified via the FIELDMOD operator and then sorted. The resulting datasets are joined and the results are output to a flat file via the Export operator.

Several things to note:

- RETL is capable of dealing with multiple data sources within a single flow.
- Although not shown in the above diagram, RETL is capable of outputting results to multiple files and/or database tables.
- RETL can perform complex transformations by combining operators.

Online Help

RETL 11.x introduces an online help system that enables flow developers to obtain operator syntax and usage information directly from the rfx binary. The following help can be obtained:

- specific property names for each operator
- confirmation of whether a property is required or optional
- valid values for each property
- a brief description of each property
- default values for each property (if property is optional).

For more information about this feature, see the `-o` option in the section entitled [RFX Command line options](#)

Chapter 5 – Database operators

RETL provides read-write operators for three database platforms:

- Oracle
- IBM DB2
- NCR TeraData

Each of the following read-write operators is described in this chapter, along with tag usage example code:

- ORAREAD
- ORAWRITE
- DB2READ
- DB2WRITE
- TERAFOREAD
- TERAWRITE

Note: We use the term DBREAD as shorthand for any one of the ORAREAD, TERAFOREAD or DB2READ operators.

Note: We use the term DBWRITE as shorthand for any one of the ORAWRITE, TERAWRITE or DB2WRITE operators.

Note: The database write operators may implicitly drop fields when writing to the database, if fields in the incoming record schema don't exist in the database table. This will only happen when appending to an existing table, and doesn't affect database writes when specifically creating/recreating a table.

ORAREAD

Performs a read from Oracle databases. RETL 11.x uses JDBC Technology to read data out of Oracle databases.

ORAWRITE

Performs a load to Oracle databases. RETL 11.x uses SQL*Loader (sqlldr) to orawrite. There are two types of loads: direct or conventional.

DB2READ

Performs a read from DB2 databases. RETL 11.x uses JDBC Technology to read data from DB2 databases.

DB2WRITE

Performs a load to DB2 databases. RETL 11.x uses JDBC Technology to load data to DB2 databases.

TERAFERREAD

Performs a read from Teradata databases. RETL 11.x uses JDBC Technology to read data from TeraData databases.

TERAWRITE

Performs a load to TeraData databases. RETL 11.x uses native TeraData utilities (mload/fastload) to write data to the TeraData databases.

Read-write operators XML specification table

The following table outlines database read/write operators.

Note: Throughout the RETL Programmer's Guide, 'schema' can apply to the data structure that the RETL applies to a dataset (such as a 'schema file'), or 'schema' can apply to the database owner of a table (the 'schemaowner' property of a database write operator).

OPERATOR Type (attribute)	Sub-Tag Name	Property Name	Property Value	Description
ORAREAD				
	PROPERTY	dbname	database name (ORACLE_SID)	Name of the Oracle database.
	PROPERTY	connectstring	username/passw ord	Database login name and password separated by a forward slash - "/".
	PROPERTY	maxdescriptors	number	Maximum number of columns allowed to be returned from the database. This is an optional property. The default value is 70.

OPERATOR Type (attribute)	Sub-Tag Name	Property Name	Property Value	Description
	PROPERTY	query		<p>The SQL query (select statement) used to extract the data from the database. SQL syntax must be executable for the database environment.</p> <p>Note: This property must be enclosed in a CDATA tag in order to allow all SQL query types. See examples for more information.</p> <p>Note: If any kind of function is applied to a column in the select statement, the column will be extracted as a DFLOAT even if the column in the database is defined as an int or string type. You may have to perform a CONVERT to change datatypes in order to compensate for this behavior.</p>
	PROPERTY	datetotimestamp	“true” or “false”	<p>This is an optional property. When set to “true”, ORAREAD returns DATE columns with the time included. When false, the time is not included. The default for this property is “false”.</p>
	PROPERTY	hostname	Hostname or IP address	<p>This is an optional property. The fully-specified hostname or IP address where the database resides. This defaults to the localhost if not specified.</p> <p>Note: This property should only be specified when it is known that connections are being made to a remote database</p> <p>Note: This may be specified as a default in rfx.conf for convenience.</p>

OPERATOR Type (attribute)	Sub-Tag Name	Property Name	Property Value	Description
	PROPERTY	port	Port number	<p>This is a required property. The port on which the database resides. This defaults to 1521 if not specified in an operator or in rfx.conf.</p> <p>Note: There are defaults that come preset in rfx.conf for the necessary port numbers. The default for Oracle is 1521. The Oracle utility 'tnsping' may be used to obtain the port number.</p> <p>Note: Verify with your database administrator the proper port for your database installation.</p>
	PROPERTY	sp_prequery	string	<p>This is a special query that allows the flow developer to specify a stored procedure to be run prior to the main query that ORAREAD executes. The current implementation does not allow variables to be specified nor does it allow data to be returned.</p>
	PROPERTY	sp_postquery	string	<p>This is a special query that allows the flow developer to specify a stored procedure to be run after the main query that ORAREAD executes. The current implementation does not allow variables to be specified nor does it allow data to be returned.</p>
	OUTPUT	name.v		The output dataset name.
ORAWRITE				
	PROPERTY	allowedrejects	number >= 0	<p>Optional property. A value greater than zero indicates how many errors are allowed sql*loader exits with a critical error. If not specified, the oracle default of 50 rejects will be used</p>
	PROPERTY	dbname	Database name (ORACLE_SID)	Name of the Oracle database.

OPERATOR Type (attribute)	Sub-Tag Name	Property Name	Property Value	Description
	PROPERTY	dbuserid	username/password	Database login name and password separated by a forward slash - “/”.
	PROPERTY	maxdescriptors	number	Maximum number of columns allowed to be written to the database.
	PROPERTY	schemaowner	schema name	The database owner of the table.
	PROPERTY	tablename	table name	Name of the Oracle table to which the data is written.
	PROPERTY	method	“direct” or “conventional”	<p>This is an optional property to specify the loading method. The default is “conventional”.</p> <p>Direct - load the data using SQL*Loader utility with direct=true.</p> <p>Conventional - Load the data using SQL*Loader utility with direct=false.</p> <p>Note: RETL 11.1 currently uses JDBC technology to load data into Oracle. RETL 11.1 will implement the native SQL*Loader utility.</p>
	PROPERTY	mode	“append” or “truncate”	<p>This is an optional property.</p> <p>Append – add the new data in addition to existing data on the target table. Truncate – delete the data from the target table before loading the new data. The default value is “append.”</p>

OPERATOR Type (attribute)	Sub-Tag Name	Property Name	Property Value	Description
	PROPERTY	createtablemode	“recreate” or “create”	<p>This is an optional property that allows the developer to specify table creation mode. If this property is not given, the flow will fail if the specified table does not already exist.</p> <p>recreate – drops the table and recreates the same table before writing the data.</p> <p>create – use this option when the target table being written to does not exist. It will create the table before writing the data only if the table doesn't exist.</p>
	PROPERTY	numloader	1...n	<p>Specifies the degree of parallelism by executing a number of sql*loaders running in parallel. May be specified in either conventional or direct mode, although there are certain restrictions for each (See Oracle sql*loader syntax for more information)</p> <p>Note: Multiple 'tempdir' properties should be used in conjunction with the 'numloader' property in a one-to-one mapping in order to maximize performance. For example, if running 8 ways parallel, 8 distinct temporary directories should be specified to maximize performance.</p>
	PROPERTY	tempdir	temporary directory	<p>The temporary directories to use for the sql*loader datafiles. May be specified multiple times by specifying separate properties</p> <p>Note: In order to maximize performance, temporary directories should reside on separate disk controllers when specifying tempdir with parallel sql*loaders via the 'numloader' property.</p>

OPERATOR Type (attribute)	Sub-Tag Name	Property Name	Property Value	Description
	PROPERTY	rows	any number	Rows per commit (default is 5000). Configurable parameter used to tweak performance. This value may be increased to realize better performance by decreasing the number of commits per sql*loader session.
	PROPERTY	sortedindexes	database index name	Indicates data sent to sql*loader exists in the same order as the specified database index. This eliminates the need to sort the new index entries and can give considerable performance increases when the sorted order of the records is known to match the index. Multiple sort indexes can be separated by commas. May be used in direct mode only
	PROPERTY	singlerow	yes or no	Specify 'yes' to update indexes as each new row is inserted. Default value is 'no'. Note: 'singlerow' should only be specified as 'yes' when it has been shown to increase performance. In most cases, it will make the load slower. Consult the Oracle's sql*loader documentation for more information about the SINGLEROW option and when it makes sense to use.
	PROPERTY	preload	string	This is a special query that allows the flow developer to specify a stored procedure to be run prior to sql*loader execution. The current implementation does not allow variables to be specified nor does it allow data to be returned. This is useful, for example, to drop indexes prior to a load.

OPERATOR Type (attribute)	Sub-Tag Name	Property Name	Property Value	Description
	PROPERTY	postload	string	This is a special query that allows the flow developer to specify a stored procedure to be run after sql*loader execution. The current implementation does not allow variables to be specified nor does it allow data to be returned. This is useful, for example, to rebuild indexes after a load.
	PROPERTY	hostname	Hostname or IP address	This is an optional property. The fully-specified hostname or IP address where the database resides. This defaults to the localhost if not specified. Note: This property should only be specified when it is known that connections are being made to a remote database Note: This may be specified as a default in rfx.conf for convenience.
	PROPERTY	port	Port number	This is a required property. The port on which the database resides. This defaults to 1521 if not specified in an operator or in rfx.conf. Note: There are defaults that come preset in rfx.conf for the necessary port numbers. The default for Oracle is 1521. The Oracle utility 'tnsping' may be used to obtain the port number. Note: Verify with your database administrator the proper port for your database installation.
	PROPERTY	tablespace	tablespace name	This option applies when using the recreate or create option. The new table create is assigned to the specified tablespace. Otherwise the tablespace defaults to the USERID.

OPERATOR Type (attribute)	Sub-Tag Name	Property Name	Property Value	Description
	INPUT	name.v		The input dataset name.
DB2READ				
	PROPERTY	dbname	database name	Name of the DB2 database.
	PROPERTY	userid	username	Database login name.
	PROPERTY	password	password	Database login password.
	PROPERTY	maxdescriptors	number	Maximum number of columns allowed to be returned from the database.
	PROPERTY	query		<p>The SQL query (select statement) used to extract the data from the database. SQL syntax must be executable for the database environment.</p> <p>Note: If any kind of function is applied to a column in the select statement, the column will be extracted as a DFLOAT even if the column in the database is defined as an int or string type. You may have to perform a CONVERT to change datatypes in order to compensate for this behavior.</p> <p>Note: This property must be enclosed in a CDATA tag in order to allow all SQL query types. See examples for more information.</p>
	PROPERTY	hostname	Hostname or IP address	<p>This is an optional property. The fully-specified hostname or IP address where the database resides. This defaults to the localhost if not specified.</p> <p>Note: This property should only be specified when it is known that connections are being made to a remote database.</p> <p>Note: This may be specified as a default in rfx.conf for convenience.</p>

OPERATOR Type (attribute)	Sub-Tag Name	Property Name	Property Value	Description
	PROPERTY	port	Port number	This is an optional property. The port on which the database resides. This defaults to 1521 if not specified in an operator or in rfx.conf. Note: There are defaults that come preset in rfx.conf for the necessary port numbers. Note: verify with your database administrator the proper port for your database installation..
	OUTPUT	name.v		The output dataset name..
DB2WRITE				
	PROPERTY	dbname	database name	Name of the DB2 database.
	PROPERTY	Userid	username	Database login name.
	PROPERTY	password	password	Database login password.
	PROPERTY	maxdescriptors	number	Maximum number of columns allowed to be written to the database.
	PROPERTY	schemaowner	schema name	The database owner of the table.
	PROPERTY	tablename	table name	Name of the DB2 table where the data is written.
	PROPERTY	tablespace	tablespace name	This option applies when using the recreate or created option. The new table create is assigned to the specified tablespace. Otherwise the tablespace defaults to the USERID.
	PROPERTY	method	“direct” or “conventional”	Direct: loads the data using autoloader utilities in DB2. Conventional: loads the data using the db2load utilities in DB2.

OPERATOR Type (attribute)	Sub-Tag Name	Property Name	Property Value	Description
	PROPERTY	mode	“insert”, “replace”, “restart”, or “terminate”	<p>This optional property performs the appropriate action as per the “IBM DB2 Universal Command Reference version 7”:</p> <p>insert - Adds the loaded data to the table without changing the existing table data (default).</p> <p>replace - Deletes all existing data from the table, and inserts the loaded data.</p> <p>restart – Restarts a previously interrupted load operation. The load operation automatically continues from the last consistency point in the load, build, or delete phase.</p> <p>terminate - Terminates a previously interrupted load operation, and rolls back the operation to the point in time at which it started.</p>
	PROPERTY	createtablemode	“recreate” or “create”	<p>Recreate: drops the table and recreates the same table, before writing the data.</p> <p>Create: use this option when the target table being written to does not exist. It creates the table before writing the data.</p> <p>If this property is not specified, RETL assumes the target table already exists and will write to the table immediately.</p>
	PROPERTY	primaryindex	comma separated list of columns.	<p>This optional parameter is a comma-separated list of indexes that allows a new table to be created with primary indexes. If this option is not specified then the table will be created without indexes.</p>

OPERATOR Type (attribute)	Sub-Tag Name	Property Name	Property Value	Description
	PROPERTY	hostname	Hostname or IP address	<p>This is an optional property. The fully-specified hostname or IP address where the database resides. This defaults to the localhost if not specified.</p> <p>Note: This property should only be specified when it is known that connections are being made to a remote database</p> <p>Note: This may be specified as a default in rfx.conf for convenience.</p>
	PROPERTY	port	Port number	<p>This is an optional property. The port on which the database resides. This defaults to 1521 if not specified in an operator or in rfx.conf.</p> <p>Note: There are defaults that come preset in rfx.conf for the necessary port numbers.</p> <p>Note: verify with your database administrator the proper port for your database installation..</p>
TERAFERead				
	PROPERTY	connectstring	username/password	Database login name and password separated by a forward slash - "/".
	PROPERTY	dbname	database name	Name of the TeraData server.
	PROPERTY	userid	username	Database login name.
	PROPERTY	password	password	Database login password.
	PROPERTY	maxdescriptors	number	<p>Maximum number of columns allowed to be returned from the database.</p> <p>Note: This is a deprecated property and will have no effect on the operator in RETL 11.</p>

OPERATOR Type (attribute)	Sub-Tag Name	Property Name	Property Value	Description
	PROPERTY	query		<p>The SQL query (select statement) used to extract the data from the database. SQL syntax must be executable for the database environment.</p> <p>Note: This property must be enclosed in a CDATA tag in order to allow all SQL query types. See examples for more information.</p>
	PROPERTY	schemaowner	schema name	Schema owner of the schema where the TERAFOREAD operator will create log tables.
	PROPERTY	sp_prequery	string	This is a special query that allows the flow developer to specify a stored procedure to be run prior to the main query that ORAREAD executes. The current implementation does not allow variables to be specified nor does it allow data to be returned.
	PROPERTY	sp_postquery	string	This is a special query that allows the flow developer to specify a stored procedure to be run after the main query that ORAREAD executes. The current implementation does not allow variables to be specified nor does it allow data to be returned.
TERAWRITE				
	PROPERTY	allowedrejects	number >= 0	Optional property. A value greater than zero indicates how many errors are allowed sql*loader exits with a critical error. If not specified, the oracle default of 50 rejects will be used
		dbname	database name	Name of the TeraData database.
		userid	username	Database login name.
		password	password	Database login password.

OPERATOR Type (attribute)	Sub-Tag Name	Property Name	Property Value	Description
		maxdescriptors	number	Maximum number of columns allowed to be written to the database. Note: This is a deprecated property and will have no effect on the operator in RETL 11.
		schemaowner	schema name	The database owner of the table.
		tablename	table name	Name of the TeraData table where the data is written.
		logschema	schema name	The database where the terawrite operator writes log and error tables. These tables are dropped after a successful load.
		createtablemode	“recreate” or “create”	Recreate – drops the table and recreates the same table before writing the data. Create – Use this option when the target table being written to does not exist. It creates the table before writing the data. If this property is not specified, RETL assumes the target table is already there and it will try to write to the table immediately.
		primaryindex	comma separated column names.	An optional parameter is a comma-separated list of indexes that allows a new table to be created with primary indexes. If this option is not specified then the table will be created without indexes.

OPERATOR Type (attribute)	Sub-Tag Name	Property Name	Property Value	Description
		loader	“mload” or “fastload”	<p>Optional. Specifies which Teradata utility to use to perform the database load. Defaults to “fastload” if createtablemode is “recreate” or the table does not exist. Otherwise, defaults to “mload”.</p> <p>Set to “fastload” if createtablemode is not “recreate” but the table is guaranteed to be empty.</p> <p>Set to “mload” if encountering problems with NFS-mounted datasets.</p>
	INPUT	name.v		The input dataset name.

Tag usage examples

```

<OPERATOR type="oraread">
    <PROPERTY name="dbname"          value="RETLdb"/>
    <PROPERTY name="connectstring"
value="RETLdb/rpassword"/>
    <!--Note: query must be enclosed in CDATA element
otherwise -->
    <!--      this query will contain invalid XML!
-->
    <PROPERTY name="query">
<![CDATA[
select * from rtbl where col > 1
    ]]>
    </PROPERTY>
    <PROPERTY name="maxdescriptors"  value="100"/>
    <PROPERTY name="datetotimestamp" value="false"/>
    <OUTPUT   name="test.v"/>
</OPERATOR>

```

```

<OPERATOR type="orawrite">
<PROPERTY name="dbname"          value="RETLdb"/>
<PROPERTY name="dbuserid"   value="username/password"/>
<PROPERTY name="tablename"   value="ORG_LOC_DM"/>
<PROPERTY name="mode"        value="append"/>
<PROPERTY name="method"      value="conventional"/>
<INPUT    name="test.v"/>
</OPERATOR>

```

```

<OPERATOR type="db2read">
    <PROPERTY name="userid"   value="RETLdb"/>
    <PROPERTY name="password" value="password1"/>
    <PROPERTY name="dbname"   value="database1"/>
    <PROPERTY name="query">
<![CDATA[
select day_idnt from time_day_dm
    ]]>
    </PROPERTY>

```

```

<OUTPUT name="test.v"/>
</OPERATOR>

<OPERATOR type="db2write">
  <PROPERTY name="userid" value="RETLdb"/>
  <PROPERTY name="password" value="rpassword"/>
  <PROPERTY name="dbname" value="develops"/>
  <PROPERTY name="schemaowner" value="RETL"/>
  <PROPERTY name="method" value="conventional"/>
  <PROPERTY name="tablename" value="andy_temp"/>
  <PROPERTY name="mode" value="replace"/>
  <PROPERTY name="createtablemode" value="recreate"/>
<OUTPUT name="test.v"/>
</OPERATOR>

<OPERATOR type="teraferread">
  <PROPERTY name="userid" value="RETL"/>
  <PROPERTY name="password" value="develops"/>
  <PROPERTY name="dbname" value="msprts01"/>
  <PROPERTY name="schemaowner" value="RETL"/>
  <PROPERTY name="query">
    <![CDATA[
select * from RETLdm.maint_dim_key_dm
      ]]>
  </PROPERTY>
<OUTPUT name="test.v"/>
</OPERATOR>

<OPERATOR type="terawrite">
  <PROPERTY name="userid" value="RETL"/>
  <PROPERTY name="password" value="develops"/>
  <PROPERTY name="dbname" value="msprts01"/>
  <PROPERTY name="schemaowner" value="RETL"/>
  <PROPERTY name="logschema" value="RETLlog"/>

```

```
<PROPERTY name="tablename" value="RETLlog.temp" />  
<INPUT name="test.v" />  
</OPERATOR>
```

Chapter 6 – Input and output operators

Each of the following input and output operators is described in this chapter, along with tag usage example code:

- DEBUG
- NOOP
- EXPORT
- IMPORT

DEBUG

Reads the records from a single input dataset and prints all records to standard output

NOOP

The NOOP acts as a terminator for datasets. In short it does nothing with the data – just throws it away.

EXPORT

Writes a RETL dataset to a flat file, either as delimited or fixed-length records, depending upon the schema.

IMPORT

Imports a flat file into RETL, translating the data file into a RETL dataset.

Input and output operators XML specification table

OPERATOR Type (attribute)	Sub-Tag Name	Property Name	Property Value	Description
DEBUG				
	INPUT	name.v		The input dataset name.
NOOP				
	INPUT	name.v		The input dataset name.
IMPORT				
	PROPERTY	inputfile	input data file	The name of the text file to import into RETL.
	PROPERTY	schemafilename	schema file	The name of the schema file describing the layout of the data file.
	PROPERTY	rejectfile	reject file	Optional property. The name of the file where records that do not match the input schema are deposited.
	PROPERTY	allowedrejects	number ≥ 0	Optional property. A value greater than zero indicates how many errors are allowed before rfx exits with a critical error. A zero indicates that any number of errors will be accepted (this is the default setting). Note: The allowedrejects property is only valid when the 'rejectfile' property is specified.
	OUTPUT	name.v		The output dataset name.
EXPORT				
	PROPERTY	outputfile	output data file	The output text file name.
	PROPERTY	outputmode	"overwrite" or "append"	Optional property specifies whether export overwrites an existing file or appends to it. Default is to overwrite.

OPERATOR Type (attribute)	Sub-Tag Name	Property Name	Property Value	Description
	PROPERTY	schemafile	schema file	<p>Optional property. The schema file describing the layout of the output file. If not specified, uses current schema (as output from the previous dataset). The default delimiter (‘ ’) is used if no schema file is specified.</p> <p>Note: This property may be used to reorder and/or drop fields from the output and reformat the fixed length, delimiter and/or nullvalue characteristics of the schema. However, if there are incompatible changes between the incoming schema and output schemafile, RETL will print warning messages.</p>
	INPUT	name.v		The output dataset name.

Tag usage examples

```
<OPERATOR type="import" name="import1,0">
<PROPERTY name="inputfile" value="import.dat"/>
<PROPERTY name="schemafile"
value="ImportOp.schema"/>
<OUTPUT name="test.v"/>
</OPERATOR>
```

```
<OPERATOR type="import" name="import1,0">
<PROPERTY name="inputfile" value="import.dat"/>
<PROPERTY name="schemafile"
value="ImportOp.schema"/>
<PROPERTY name="allowedrejects" value="100"/>
<PROPERTY name="rejectfile" value="import.rej"/>
<OUTPUT name="test.v"/>
</OPERATOR>
```

```
<OPERATOR type="export" name="export1,0">  
  <PROPERTY name="outputfile" value="output.dat"/>  
  <PROPERTY name="schemafilename" value="outputOp.schema"/>  
  <INPUT name="test.v"/>  
</OPERATOR>
```

Chapter 7 – Join operators

RETL provides the following join operators, each of which is described in this chapter:

- INNERJOIN
- LEFTOUTERJOIN
- RIGHTOUTERJOIN
- FULLOUTERJOIN
- LOOKUP

Note: For INNERJOIN, LEFTOUTERJOIN, RIGHTOUTERJOIN and FULLOUTERJOIN the input datasets must be sorted on the key. LOOKUP does not require sorted input.

INNERJOIN

Transfers records from both input datasets whose key fields contain equal values to the output dataset. Records whose key fields do not contain equal values are dropped.

LEFTOUTERJOIN

Transfers all values from the left dataset, and transfers values from the right dataset only where key fields match. The operator drops the key field from the right dataset. Otherwise, the operator writes default values.

RIGHTOUTERJOIN

Transfers all values from the right dataset, and transfers values from the left dataset only where key fields match. The operator drops the key field from the left dataset. Otherwise, the operator writes default values.

FULLOUTERJOIN

For records that contain key fields with identical and dissimilar content, the FULLOUTERJOIN operator transfers records from both input datasets to the output dataset.

LOOKUP

Similar to the INNERJOIN operator. However, there is no need to do a sort on the input datasets. Looks up a value from one dataset whose key fields match the lookup dataset and outputs the matching values.

When using a lookup in multiple partitions be sure to “hash” the source dataset but not the lookup dataset. Remember also that the lookup dataset must be small enough to fit in memory otherwise severe performance problems may result. If in doubt as to whether the lookup dataset will fit in memory always use INNERJOIN or OUTERJOIN.

Special notes about Join operators

Join operators will ‘favor’ data fields from the ‘dominant’ side (usually, the first INPUT to the operator) when joining datasets that contain the same non-key fields on each side. For example,

Left DataSet

Key	Same Non-Key field	Non-Key field
A	B	C

Right DataSet

Key	Same Non-Key field	Non-Key field
A	B	D

“Joined” dataset

Operator	Key	Same Non-Key field	Non-Key field	Non-Key field
Innerjoin	A	B (from LHS)	C	D
Leftouterjoin	A	B (from LHS)	C	D
Rightouterjoin	A	B (from RHS)	C	D
Fullouterjoin	A	left_B, right_B (from LHS)	C	D
Lookup	A	B (from LHS)	C	D

It is important to notice that `fullouterjoin` will rename the datafields that have the same name on each dataset, to `left_<shared column name>` and `right_<shared column name>`. It is recommended to drop the unneeded same-name fields from each dataset prior to joining in order to make the functionality more explicit to those maintaining your flows.

Join operators XML specification table

OPERATOR Type (attribute)	Sub-Tag Name	Property Name	Property Value	Description
INNERJOIN				
	PROPERTY	key	key field	Key columns to be joined.
	INPUT	inputname1.v		Input dataset 1 – sorted on the key columns.
	INPUT	inputname2.v		Input dataset 2 – sorted on the key columns.
	OUTPUT	outputname.v		The output dataset name.
LEFTOUTERJOIN RIGHTOUTERJOIN FULLOUTERJOIN				
	PROPERTY	key	key field	Key columns to be joined.
	PROPERTY	nullvalue	column name=<null value>	The default null value that is assigned to the null column.
	INPUT	inputname1.v		Input dataset 1. (left dataset) – sorted on the key columns
	INPUT	inputname2.v		Input dataset 2. (right dataset) – sorted on the key columns
	OUTPUT	name.v		The output dataset name.
LOOKUP				
	PROPERTY	tablekeys	key field	Comma separated key columns to be looked up.
	PROPERTY	ifnotfound	“reject”, “continue”, “drop”, or “fail”	What to do with the record if the result did not match. If not specified, this option will default to “fail”.
	PROPERTY	alldups	“true” or “false”	Optional property defaults to “true”. This property allows the lookup to return more than 1 record if the lookup dataset has more than 1 matching set of keys.
	INPUT	inputname1.v		First input dataset is always the data that needs to be processed.
	INPUT	inputname2.v		Second input dataset is always the “lookup” dataset.
	OUTPUT	resdataset.v		The first output is the successful lookup output dataset name.

OPERATOR Type (attribute)	Sub-Tag Name	Property Name	Property Value	Description
	OUTPUT	rejdataset.v		The second will contain all records not matching the “tablekeys” property. This needs to be specified if the “ifnotfound” option is set to “reject”.

Tag usage examples

```
<OPERATOR type="innerjoin" name="innerjoin,0">
  <PROPERTY name="key" value="LOC_KEY"/>
  <INPUT name="test_1.v"/>
  <INPUT name="test_2.v"/>
  <OUTPUT name="output.v"/>
</OPERATOR>
```

```
<OPERATOR type="leftouterjoin" name="leftouterjoin,0">
  <PROPERTY name="key" value="LOC_KEY"/>
  <PROPERTY name="nullvalue" value="PROD_SEASN_KEY=-1"/>
  <INPUT name="left.v"/>
  <INPUT name="right.v"/>
  <OUTPUT name="result.v"/>
</OPERATOR>
```

```
<OPERATOR type="rightouterjoin"
name="rightouterjoin,0">
  <PROPERTY name="key" value="LOC_KEY"/>
  <PROPERTY name="nullvalue" value="PROD_SEASN_KEY=-1"/>
  <INPUT name="right.v"/>
  <INPUT name="left.v"/>
  <OUTPUT name="output.v"/>
</OPERATOR>
```

```
<OPERATOR type="fullouterjoin" name="fullouterjoin,0">
  <PROPERTY name="key" value="LOC_KEY"/>
  <PROPERTY name="nullvalue" value="PROD_SEASN_KEY=-1"/>
  <INPUT name="right.v"/>
```

```
<INPUT      name="left.v" />
<OUTPUT     name="output.v" />
</OPERATOR>

<OPERATOR   type="lookup">
<PROPERTY   name="tablekeys"
             value="LOC_KEY, SUPP_KEY" />
<PROPERTY   name="ifnotfound"      value="reject" />
<INPUT      name="dataset.v" />
<INPUT      name="lookupdataset.v" />
<OUTPUT     name="result.v" />
<OUTPUT     name="reject.v" />
</OPERATOR>

<OPERATOR   type="lookup">
<PROPERTY   name="tablekeys"      value="LOC_KEY" />
<PROPERTY   name="ifnotfound"     value="continue" />
<PROPERTY   name="allowdups"      value="true" />
<INPUT      name="dataset.v" />
<INPUT      name="lookupdataset.v" />
<OUTPUT     name="result.v" />
</OPERATOR>
```

Chapter 8 – Sort and merge operators

RETL provides the following sort and merge operators, each of which is described in this chapter:

- COLLECT and FUNNEL
- SORTCOLLECT and SORTFUNNEL
- HASH
- SORT
- MERGE

COLLECT and FUNNEL

Both operators combine records from input datasets as they arrive. This can be used to combine records that have the same schema from multiple sources. Note that these operators are sometimes used implicitly by RETL to rejoin datasets that have been divided during partitioning in parallel processing environments (where the number of RETL partitions is greater than one).

SORTCOLLECT and SORTFUNNEL

Like COLLECT and FUNNEL these operators combine records from input datasets. These operators maintain sorted order of multiple datasets already sorted by the key fields. Records are collected in sorted order using a merge sort algorithm. If incoming records are unsorted, COLLECT followed by the SORT operator should be used instead.

Note: The sort order (ascending or descending) of the input datasets to sortcollect must be the same and must match the 'order' property of sortcollect. Otherwise, sortcollect may produce unexpected results.

HASH

The hash-partitioning operator examines one or more fields of each input record, called “hash key” fields, to assign records to a processing node. Records with the same values for all hash key fields are assigned to the same processing node. This type of partitioning method is useful when grouping or sorting data to perform a processing operation.

SORT

Sorts the records in the RETL dataset based on one or more key fields in the dataset.

MERGE

Merges input dataset columns record by record. Each output record is the union of the fields for each incoming record in the INPUT datasets. The number of records contained in the inputs' datasets must match. Columns are ordered by the order of the input datasets, first input dataset, second input dataset and so on.

Sort and merge operators XML specification table

OPERATOR Type (attribute)	Sub-Tag Name	Property Name	Property Value	Description
COLLECT FUNNEL				Note: These operators are aliases for each other. We use COLLECT as a general rule but either operator will work.
	INPUT	inputname1.v		Input dataset 1.
	INPUT	inputname2.v		Input dataset n. There may be 0 or more additional datasets.
	OUTPUT	outputname.v		The output dataset name.
HASH				
	PROPERTY	key	key field	Key columns to be hashed.
	INPUT	inputname.v		Input dataset.
	OUTPUT	name.v		The output dataset name.
SORT				
	PROPERTY	key	key field	Key columns to sort by.
	PROPERTY	order	“desc” or “asc”	Optional property. Set to “desc” for descending sort order and “asc” for ascending sort order. Default value is “asc”.
	PROPERTY	removedup	“true”	Optional value. If set then duplicate records will be removed. Default is false.
	PROPERTY	tmpdir	Directory	Optional property. <u>We recommend that this property not be specified.</u> Temporary directories should be specified in the rfx.conf. This property allows one to override the temporary directory to use for the sort command. Note: If used, the directory should be periodically cleaned as the TMPDIR from the rfx.conf file (see Chapter 2 above).
	INPUT	inputname.v		Input dataset.
	OUTPUT	name.v		The output dataset name.
SORTCOLLECT SORTFUNNEL				Note: These operators are aliases for each other. We use SORTCOLLECT as a general rule but either operator will work.

OPERATOR Type (attribute)	Sub-Tag Name	Property Name	Property Value	Description
	PROPERTY	key	key field	Key columns to sort by. Specify multiple keys by using multiple ‘key’ property instances. For example: <PROPERTY name=“key” value=“k1”/> <PROPERTY name=“key” value=“k2”/>
	PROPERTY	order	“desc” or “asc”	Optional property defaults describes the sort order of the incoming key fields. Default value is “asc” for ascending order. Specify “desc” if keys are sorted in descending order.
	INPUT	inputname1.v		Input dataset 1.
	INPUT	inputname_n.v		Input dataset n – can be 0 or more datasets.
	OUTPUT	resultdataset.v		Output dataset.
MERGE				
	INPUT	inputname1.v		Input dataset 1.
	INPUT	inputname_n.v		Input dataset n – this can be more than 2 datasets.
	OUTPUT	resultdataset.v		The output dataset.

Tag usage examples

```
<OPERATOR type="collect">
  <INPUT name="test_1.v"/>
  <INPUT name="test_2.v"/>
  <INPUT name="test_2.v"/>
  <OUTPUT name="output.v"/>
</OPERATOR>
```

```
<OPERATOR type="hash">
  <PROPERTY name="key" value="LOC_KEY"/>
  <INPUT name="left.v"/>
  <OPERATOR type="sort" >
  <PROPERTY name="key" value="LOC_KEY"/>
  <OUTPUT name="result.v"/>
  </OPERATOR>
</OPERATOR>
```

```
<OPERATOR type="sortcollect">  
  <PROPERTY name="key" value="LOC_KEY"/>  
  <INPUT name="test_1.v"/>  
  <INPUT name="test_2.v"/>  
  <OUTPUT name="output.v"/>  
</OPERATOR>
```

```
<OPERATOR type="merge">  
  <INPUT name="test_1.v"/>  
  <INPUT name="test_2.v"/>  
  <OUTPUT name="output.v"/>  
</OPERATOR>
```

Chapter 9 – Mathematical operators

RETL provides the following mathematical operators, each of which is described in this chapter:

- BINOP
- GROUPBY
- GROUPBY on multiple partitions

BINOP

Performs basic algebraic operations on two fields. Addition, subtraction, multiplication and division are supported for all numeric types. The left and right operands may also be defined as constants. Note that division by zero produces a null value. Only addition is supported for string fields; this becomes concatenation. Binop is not currently supported for date fields.

GROUPBY

The input to the GROUPBY operator is a dataset to be summarized; the output is a dataset containing one record for each group in the input dataset. Each output record contains the fields that define the group and the output summaries calculated by the operator. One simple summary is a count of the number of records in each group. Another kind of summary is a statistical value calculated on a particular field for all records in a group.

Note: If all rows in a column are null, the GROUPBY operator will provide a null column total.

Note: Groupby requires sorted input only in the case where keys are specified. Otherwise, sorted input is not necessary

GROUPBY on multiple partitions

When running RETL using multiple partitions, run the GROUPBY operator with the 'parallel' property set to 'true' to get the performance increase from the multiple partitions. A HASH/SORT needs to be performed before the parallel GROUPBY. If the same KEYS are used to GROUPBY that were used for the HASH/SORT, data with the same KEY set will not be spread to multiple partitions. If the next operator is a serial operator, there will be an implied FUNNEL operator called by RETL after the GROUPBY to gather the data from the different partitions together into a single dataset. If the next operator is a parallel operator, RETL will not call a FUNNEL operator and the previous HASH/SORT will be maintained. If not using the same KEYS to GROUPBY, a SORTFUNNEL is required to collect the data from the multiple partitions back into a single, sorted dataset. A final serial GROUPBY must then be performed because data may have been spread across multiple partitions and not included in the GROUPBY calculation. If the next operator is a serial operator, then nothing more needs to be done. If the next operator is a parallel operator, another HASH/SORT must be performed because the HASH/SORT from the parallel GROUPBY will not be maintained because a serial GROUPBY was performed after that.

Mathematical operators XML specification table

OPERATOR Type (attribute)	Sub-Tag Name	Property Name	Property Value	Description
BINOP				
	INPUT	inputname.v		Input dataset.
	PROPERTY	left / constleft	field name or constant value	If property name = 'left' then the column name for the left operand must be specified. If property name = 'CONSTLEFT' then a constant value must be specified.
	PROPERTY	right / constright	field name or constant value.	If property name = 'right' then the column name for the right operand must be specified. If property name = 'CONSTRIGHT' then a constant value must be specified.
	PROPERTY	dest	destination Field	The result destination field name. This can be the same field name as was specified in 'left' or 'right' properties in order to re-use existing fields.
	PROPERTY	desttype	type	Optional field. The type of the destination field. The default value is the type of the left field.
	PROPERTY	operator	'+' or '-' or '*' or '/'	'+' for addition '-' for subtraction '*' for multiplication '/' for division
	OUTPUT	outputname.v		The output dataset name.
GROUPBY				
	INPUT	input.v		Input dataset.
	PROPERTY	parallel	"true" or "false"	True – If running in multiple partitions. False – If running in a single partition (default).

OPERATOR Type (attribute)	Sub-Tag Name	Property Name	Property Value	Description
	PROPERTY	key	key field	Optional property. Key columns to groupby. If key is not specified, groupby considers all input data as one group. Note: If 'key' property isn't specified, groupby does not require sorted input
	PROPERTY	reduce	column name	Column to be summed, maxed, etc. Multiple "reduce" properties can be specified, but associated "min", "max", "sum", "first", "last", and "count" properties must be specified immediately following each reduce property.
	PROPERTY	min, max, sum, first, last, count	destination column	Type of groupby operation and assigns the column to a new column name.
	OUTPUT	name.v		The output dataset name.

Tag usage examples

```
<OPERATOR type="binop">
  <INPUT name="import.v" />
  <PROPERTY name="left" value="field1" />
  <PROPERTY name="operator" value="+" />
  <PROPERTY name="constright" value="2" />
  <PROPERTY name="dest" value="destfield" />
  <OUTPUT name="binop.v" />
</OPERATOR>
```

```
<OPERATOR type="binop">
  <INPUT name="import.v" />
  <PROPERTY name="left" value="field1" />
  <PROPERTY name="operator" value="-" />
  <PROPERTY name="right" value="field2" />
  <PROPERTY name="dest" value="destfield" />
  <OUTPUT name="binop.v" />
</OPERATOR>
```

```

<OPERATOR type="groupby">
  <INPUT name="input_1.v"/>
  <PROPERTY name="parallel" value="true"/>
  <PROPERTY name="key" value="sex"/>
  <PROPERTY name="reduce" value="age"/>
  <PROPERTY name="min" value="min_age"/>
  <PROPERTY name="max" value="max_age"/>
  <PROPERTY name="first" value="first_age"/>
  <PROPERTY name="last" value="last_age"/>
  <PROPERTY name="count" value="count_age"/>
  <PROPERTY name="sum" value="sum_age"/>
  <PROPERTY name="reduce" value="birthday"/>
  <PROPERTY name="min" value="min_birthday"/>
  <PROPERTY name="max" value="max_birthday"/>
  <PROPERTY name="first" value="first_birthday"/>
  <PROPERTY name="last" value="last_birthday"/>
  <PROPERTY name="count" value="count_birthday"/>
  <OUTPUT name="output.v"/>
</OPERATOR>

```

The following example shows what happens if the dataset was previously hashed and sorted on a different key than the group by key in the “groupby” operator, and if the groupby was run in multiple partitions.

In this case an additional “sortcollect” and “groupby” operator needs to be used to guarantee the correct result.

```

<OPERATOR type="hash">
  <PROPERTY name="key" value="ZIP_CODE"/>
  <PROPERTY name="key" value="NAME"/>
  <OPERATOR type="sort">
    <PROPERTY name="key" value="ZIP_CODE"/>
    <PROPERTY name="key" value="NAME"/>
    <OUTPUT name="output1.v"/>
  </OPERATOR>
</OPERATOR>
<OPERATOR type="groupby">
  <INPUT name="output1.v"/>
  <PROPERTY name="parallel" value="true"/>
  <PROPERTY name="key" value="sex"/>

```

```
<PROPERTY name="reduce" value="age" />
<PROPERTY name="count" value="count_age" />
<PROPERTY name="reduce" value="birthday" />
<PROPERTY name="max" value="max_birthday" />
<OPERATOR type="sortcollect">
  <PROPERTY name="key" value="sex" />
  <OPERATOR type="groupby">
    <PROPERTY name="parallel" value="true" />
    <PROPERTY name="key" value="sex" />
    <PROPERTY name="reduce" value="age" />
    <PROPERTY name="count" value="count_age" />
    <PROPERTY name="reduce" value="birthday" />
    <PROPERTY name="max"
value="max_birthday" />
    <OUTPUT name="output2.v" />
  </OPERATOR>
</OPERATOR>
</OPERATOR>
```

Chapter 10 – Structures and data manipulation operators

RETL provides the following operators for the manipulation of structures and data, each of which is described in this chapter:

- CONVERT
- FIELDMOD
- FILTER
- GENERATOR
- REMOVEDUP

CONVERT

The convert operator is used to convert an existing datatype to a new datatype from an input dataset. The following paragraph describes the syntax of the CONVERT property.

- The root tag <CONVERT>, containing one or more <CONVERTFUNCTION> or <TYPEPROPERTY> tags
- The <CONVERT> tag requires the following attributes:
 - *Destfield*: destination field name or new name.
 - *Sourcefield*: original field name or old field name.
 - *Newtype*: new datatype
 - The <CONVERTFUNCTION> tag allows conversion of a column from one data type to a different data type and has the following attributes:
 - *name* - The value of name of the conversion function determines what conversion is done. The name generally follows the form: <typeTo>_from_<typeFrom>. Conversions are defined between all numeric values and from numbers to strings as well. The table below shows some example conversions.
 - The <TYPEPROPERTY> tag allows turning the column into nullable or not null and has the following attributes:
 - *name*: nullable
 - *value*: “true” or “false”

Conversion functions

There are many conversion functions to allow conversion between types. Much of this is done with default conversions between types (see [Appendix A – Default Conversions](#)). When using a default conversion you simply specify “default” as the name of the conversion.

Here are the other (non-default) conversion functions:

Conversion Name	Description
make_not_nullable	Converts nullable field to not null; requires functionarg tag. See the “Tag usage examples,” section later in this chapter.
make_nullable	Converts non-nullable field to nullable field; requires functionarg tag.
string_length	Converts a string to a UINT32 with a value equivalent to the string’s length.
string_from_int32	Converts to STRING from INT32.
string_from_int64	Converts to STRING from INT64.
string_from_int16	Converts to STRING from INT16.
string_from_int8	Converts to STRING from INT8.
int32_from_dfloat	Converts to INT32 from DFLOAT rounding the result to the nearest integer value.
int64_from_dfloat	Converts to INT64 from DFLOAT rounding the result to the nearest integer value.
string_from_date	Converts to STRING from DATE.
dfloat_from_string	Converts to DFLOAT from STRING.
string_from_dfloat	Converts to STRING from DFLOAT.

Note: RETL will report invalid conversions, but RETL doesn’t handle certain conversions well. Care should be taken to ensure that the data is well formed by the time a conversion takes place. Currently overflow and/or underflow conversion errors are not detected by RETL. For example, converting the INT16 “-12” to a UINT16 will result in undefined behavior.

FIELDMOD

Used to remove, duplicate, drop and rename columns within RETL. There are several optional parameters that you can use in the fieldmod operator. Here are some notes on how to use the fieldmod operator:

- Use the keep property when you need to drop a large number of columns and/or ignore columns that you don't know about (allowing your flows to be more resilient to change). Any columns that are not specified in the “keep” property will be dropped. The column names are separated by a space. Multiple keep properties can be specified.
- If you want keep most of columns and just drop a few columns, use the “drop” property. The columns to drop are separated by a space. The drop property is processed after the keep property, which means a column is dropped if it is specified on both keep and drop property. Multiple drop properties can be specified. Duplicated columns in single or multiple drop properties will generate an error, for example, “Delete of field failed (field 'Emp_Age' not found)” since the column has been dropped.
- The “rename” and “duplicate” properties affect the dataset after keep and drop properties have been processed. If you attempt to rename or duplicate a column that has been dropped, RFX will generate an error (e.g. Error: the column 'Emp_Name' has been dropped and can not be duplicated).

FILTER

Used to filter a dataset into two categories:

- Those that meet the filter criterion and,
- Those that do not.

Some uses might be to: filter records where a field must be equivalent to a certain string, filter on records where a certain field is less than 10, or filter on records where two fields are equal. This is somewhat like the WHERE clause of a SQL statement.

GENERATOR

Used to create new datasets for testing or for combining with other data sources. It can act as a standalone operator that generates the dataset from scratch, or as an operator that can add fields to an existing dataset. The following paragraph describes the syntax of the “SCHEMA” property, which in the example below, is represented within the **CDATA** tag.

The SCHEMA property should specify the XML that will generate the fields. The basic outline is:

- The root tag <GENERATE>, containing one or more <FIELD> tags
- The <FIELD> tag specifies the “name” and “type” of the field as attributes, and can contain exactly one field generation tag. Field generation tags include:
 - <SEQUENCE> with the following attributes:
 - *init*: starting number in sequence. The default is “0”.
 - *incr*: increment to add for each record in sequence. The default is “1”.
 - *limit*: max number, once reached, will start from beginning. Optional, unlimited if not specified.
 - *partnum_offset*: (true/false) will add the partition number to the init value for parallel operation. The default is false.
 - *partcount_incr*: (true/false) will multiply the incr value by the number of partitions. The default is false.
 - The <CONST> tag allows the specification of a single attribute, *value*, which is the value that the field will take on.
 - The <VALUELIST> tag has no attributes, but has multiple <CONST> tags within it, specifying the list of values that should be cycled through

The following are the only data types that can be used within the GENERATOR operator:

- int8
- int16
- int32
- int64
- dfloat
- string
- date

REMOVEDUP

The REMOVEDUP operator performs a record-by-record comparison of a sorted dataset to remove duplicate records. Duplicates are determined based upon the key fields specified.

Structures and data manipulation operators XML specification table

OPERATOR Type (attribute)	Sub-Tag Name	Property Name	Property Value	Description
CONVERT				
	INPUT	input.v		This property is optional. If specified, this is the input dataset.
	PROPERTY	convertspec		Describes the new column data structure to be converted. See the convert specification and the example for more detail.
	OUTPUT	name.v		The output dataset name.
FIELDMOD				
	INPUT	input.v		This property is optional. If specified, this is the input dataset.
	PROPERTY	keep	column_name	This optional property is a space-separated list of the columns to be kept - the named fields will be retained and all others will be dropped. This property may be specified multiple times.
	PROPERTY	drop	column_name	This optional property is a space-separated list of the columns to be dropped - the named fields will be dropped and all other fields will be retained. This property may be specified multiple times.
	PROPERTY	rename	new_column_name =old_column_name	Column to be renamed. The new column name is separated by an equal sign from the old column name.
	PROPERTY	duplicate	column_name =target_colmn_name	Duplicate one column to another column. The source column is separated by an equal sign from the target column name.
	OUTPUT	name.v		The output dataset name.

OPERATOR Type (attribute)	Sub-Tag Name	Property Name	Property Value	Description																								
FILTER																												
	INPUT	inputname.v		Input dataset.																								
	PROPERTY	filter	Filter expression	<p>The following operations are supported:</p> <table border="1"> <thead> <tr> <th>Operation</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>"NOT"</td> <td>Logical NOT</td> </tr> <tr> <td>"AND"</td> <td>Logical AND</td> </tr> <tr> <td>"OR"</td> <td>Logical OR</td> </tr> <tr> <td>"IS_NULL"</td> <td>True if field is null.</td> </tr> <tr> <td>"IS_NOT_NULL"</td> <td>True if field is not null.</td> </tr> <tr> <td>"GE"</td> <td>Logical >=</td> </tr> <tr> <td>"GT"</td> <td>Logical ></td> </tr> <tr> <td>"LE"</td> <td>Logical <=</td> </tr> <tr> <td>"LT"</td> <td>Logical <</td> </tr> <tr> <td>"EQ"</td> <td>True if right and left fields are equal.</td> </tr> <tr> <td>"NE"</td> <td>True if right and left fields are not equal.</td> </tr> </tbody> </table>	Operation	Description	"NOT"	Logical NOT	"AND"	Logical AND	"OR"	Logical OR	"IS_NULL"	True if field is null.	"IS_NOT_NULL"	True if field is not null.	"GE"	Logical >=	"GT"	Logical >	"LE"	Logical <=	"LT"	Logical <	"EQ"	True if right and left fields are equal.	"NE"	True if right and left fields are not equal.
Operation	Description																											
"NOT"	Logical NOT																											
"AND"	Logical AND																											
"OR"	Logical OR																											
"IS_NULL"	True if field is null.																											
"IS_NOT_NULL"	True if field is not null.																											
"GE"	Logical >=																											
"GT"	Logical >																											
"LE"	Logical <=																											
"LT"	Logical <																											
"EQ"	True if right and left fields are equal.																											
"NE"	True if right and left fields are not equal.																											
	PROPERTY	rejects	"true" or "false"	Optional filter value whose default value is false. If true then the operator will expect a second OUTPUT to be specified into which rejected (i.e. filtered) records will be deposited.																								
	OUTPUT	name.v		The first output dataset specified contains all of the records for which the filter expression was true.																								
	OUTPUT	reject.v		This property is required if the "rejects" property (above) is specified. This output dataset is the set of records that did not meet the filter condition.																								
GENERATOR																												

OPERATOR Type (attribute)	Sub-Tag Name	Property Name	Property Value	Description
	INPUT	input.v		This property is optional. If specified, this is the input dataset.
	PROPERTY	parallel	“true” or “false”	True – if generator option should be run in parallel. False – if generator option should be run in a single partition (default).
	PROPERTY	numrecords	1..n	This optional field is used when no INPUT is specified to determine how many records are generated. If an input is specified this value is ignored. The default value is 1.
	PROPERTY	schema		Describes the new column data structure to be generated. See the generator specification and the example for more detail.
	OUTPUT	name.v		The output dataset name.
REMOVEDUP				
	INPUT	input.v		This property is optional. If specified, this is the input dataset.
	PROPERTY	key	column_name	Columns that have the same data to be removed. More than one column property can be specified.
	PROPERTY	keep	first or last	Either keeps the first or last data if key fields are the same. It will default to first. Note: ‘first’ should be specified as the value for the ‘keep’ property when sort order makes it possible. This will increase the speed upon which removedup operates.
	OUTPUT	name.v		The output dataset name.

Tag usage examples

```

<OPERATOR type="filter">
  <INPUT      name="input.v" />
  <PROPERTY name="filter"
            value="SSN EQ '123456789' AND
SALARY GT '124.22' AND
DOB LT '19981010'"/>
  <PROPERTY name="rejects" value="true"/>
  <OUTPUT    name="valid.v" />
  <OUTPUT    name="reject.v" />
</OPERATOR>

<OPERATOR type="generator">
  <PROPERTY name="numrecords" value="5"/>
  <PROPERTY name="schema">
    <![CDATA[
      <GENERATE>
        <FIELD name="DM_REC'D_LOAD_DT"
type="date"
          nullable="false">
          <CONST value="19800101"/>
        </FIELD>
        <FIELD name="LOC_KEY"
type="int8"  nullable="true">
          <SEQUENCE init="1" incr="1"/>
        </FIELD>
      </GENERATE>
    ]]>
  </PROPERTY>
</OPERATOR>

<OPERATOR type="generator">
  <INPUT      name="input.v"/>
  <PROPERTY name="schema">
    <![CDATA[
      <GENERATE>

```

```

                                <FIELD name="F_FULL_PO_COUNT"
type="int64"
nullable="true">
                                <CONST value="1"/>
                                </FIELD>
                                <FIELD name="F_PART_PO_COUNT"
type="int64"
nullable="true">
                                <CONST value="0"/>
                                </FIELD>
                                </GENERATE>
                                ]]>
                                </PROPERTY>
                                <OPERATOR type="debug"/>
                                </OPERATOR>

<OPERATOR type="convert">
    <INPUT      name="input.v"/>
    <PROPERTY name="convertspec">
        <![CDATA[
            <CONVERTSPECS>
                <CONVERT destfield="SUPP_IDNT"
                    sourcefield="SUPPLIER"
                    newtype="string">
                    <CONVERTFUNCTION
name="string_from_int64"/>
                </CONVERT>
                <CONVERT destfield="LOC_IDNT"
                    sourcefield="LOCATION"
                    newtype="string">
                    <CONVERTFUNCTION
name="string_from_int32"/>
                <TYPEPROPERTY name="nullable"
value="true"/>
                </CONVERT>
            </CONVERTSPECS>
        ]]>
    </PROPERTY>

```

```

        <OPERATOR type="debug" />
    </OPERATOR>

<OPERATOR type="removedup">
    <INPUT name="input.v" />
    <PROPERTY name="key" value="SKU_KEY" />
    <PROPERTY name="key" value="LOC_KEY" />
    <PROPERTY name="keep" value="LAST" />
    <OUTPUT name="output.v" />
</OPERATOR>

<OPERATOR type="fieldmod">
<INPUT name="input.v" />
    <PROPERTY name="keep" value="Emp_Name
Emp_Age" />
    <PROPERTY name="keep" value="Emp_ID" />
<OUTPUT name="output.v" />
</OPERATOR>

<OPERATOR type="fieldmod">
<INPUT name="input.v" />
    <PROPERTY name="rename"
value="Emp_Name=EmpName" />
<OUTPUT name="output.v" />
</OPERATOR>

<OPERATOR type="fieldmod">
<INPUT name="input.v" />
    <PROPERTY name="drop" value="Emp_Title" />
<OUTPUT name="output.v" />
</OPERATOR>

<OPERATOR type="fieldmod">
<INPUT name="input.v" />
    <PROPERTY name="duplicate" value="Emp_Name=Name" />
<OUTPUT name="output.v" />
</OPERATOR>

```

```
<OPERATOR type="convert">
  <INPUT name="inv_sbc_lw_dm.v"/>
  <PROPERTY name="convertspec">
    <![CDATA[
      <CONVERTSPECS>
        <CONVERT destfield="SBCLASS_KEY"
          sourcefield="SBCLASS_KEY">
          <CONVERTFUNCTION
name="make_not_nullable">
            <FUNCTIONARG name="nullvalue"
value="-1"/>
          </CONVERTFUNCTION>
        </CONVERT>
      </CONVERTSPECS>
    ]]>
    <OUTPUT name="converted.v"/>
  </PROPERTY>
</OPERATOR/>
```


Chapter 11 – Other operators

This chapter describes these RETL operators and their usage:

- COMPARE
- SWITCH
- CHANGECAPTURE
- COPY
- DIFF
- CLIPROWS

COMPARE

Performs a field-by-field comparison of records in two presorted input datasets. This operator compares the values of top-level, non-vector data types such as strings. All appropriate comparison parameters are supported (for example, case sensitivity and insensitivity for string comparisons). The assumption is that the original dataset is used as a basis for the comparison to the second dataset. The comparison results are recorded in the output dataset.

Appends a compare 'result' to beginning of each record with a value set as follows depending upon the outcome of the comparison:

Code	Other
-1	first dataset FIELD is LESSTHAN second dataset FIELD
0	first dataset FIELD is the same as second dataset FIELD
1	first dataset FIELD is GREATER THAN second dataset FIELD
-2	record doesn't exist in first dataset
2	record doesn't exist in second dataset

Here is an example to illustrate:

Original Key	Compare Key
A	A
B	A
C	
D	E

The resulting output would look like this:

Key	result	Compare Result
A	0	Keys match
B	1	Original key is greater than compare key
C	-1	Original key is less than compare key
D	2	Original key doesn't exist in the compare dataset

Note that the “Compare result” column above is just for illustration. Only the “result” above would be added to the actual output dataset.

SWITCH

Assigns each record of an input dataset to an output dataset, based on the value of a specified field.

CHANGECAPTURE

Use CHANGECAPTURE to compare two datasets. The assumption is that the flow is comparing an original dataset with a modified copy (changed) dataset. The output is a description of what modifications have been made to the original dataset. Here are the changes that are captured:

- Inserts: records added to the original dataset.
- Deletes: records deleted from the original dataset.
- Edits: records matching the given keys fields whose other fields have values have been modified from the original records.
- Copies: records not changed from the original.

The operator works based on these conditions:

- Two inputs (the original and changed datasets), one output containing the combination of the two (edits are taken from the modified side) and a new field to show what change (if any) occurred between the original and the changed dataset.
- The two input datasets must have the same schemas
- The two datasets must be previously sorted on specified key fields

CHANGECAPTURE identifies duplicate records between two datasets by comparing specified key fields. It then compares the value of the fields between the two datasets. The operator adds a field to the output records that contain one of four possible values, representing the conditions noted earlier (inserts, deletes, edits, or copies). The actual values assigned to each of the possibilities can be changed from the default if desired. It is possible to assign the name of this field and to indicate that records falling into one or more of the above categories be filtered from the output dataset, rather than being passed along with the change code.

Here is an example to illustrate:

Original Dataset			Changed Dataset		
Key	Value	Other	Key	Value	Other
John	5	corn	John	5	corn
Jill	10	beans	George	7	olives
Allie	2	pizza	Allie	5	pizza
Frank	14	42fas	Frank	14	Bogo

The resulting OUTPUT would look like this:

Key	Value	Other	Change	CodeField
John	5	corn	copy	2
Jill	10	beans	deletion	1
George	7	olives	insertion	0
Allie	5	pizza	edit	3
Frank	14	bogo	copy	2

Note that the “Change” column above is just for illustration. Only the “codefield” above would be added to the actual output dataset.

CHANGECAPTURE is often used in conjunction with the SWITCH operator.

COPY

The COPY operator copies a single input dataset to one or more output datasets.

DIFF

The DIFF operator performs a record-by-record comparison of two versions of the same dataset (the ‘before’ and ‘after’ datasets) and outputs one dataset that contains the difference between the compared datasets. Diff is very similar to ChangeCapture – the only differences are the default change codes and default drops. ChangeCapture is the recommended operator to use for these types of operations, and Diff is provided simply for backwards compatibility.

CLIPROWS

The CLIPROWS operator performs a record-by-record comparison of a sorted dataset to “clip” a number of rows from a group of records. For each group value of the input keys it will return up to the first or last N entries in the group. It sends to its OUTPUT dataset the given records for further processing and discards the rest.

Other operators XML specification table

OPREATOR Type (attribute)	Sub-Tag Name	Property Name	Property Value	Description
COPY				
	INPUT	inputname.v		The input dataset.
	OUTPUT	output1.v		The output dataset 1.
	OUTPUT	output2.v		The output dataset 2.
COMPARE				
	INPUT	input_1.v		Input dataset 1.
	INPUT	input_2.v		Input dataset 2.
	PROPERTY	key	column_name	Column name to be compared between the two datasets defined above.
	OUTPUT	name.v		Output dataset.
CLIPROWS				
	INPUT	input.v		Input dataset.
	PROPERTY	key	column_name	Required property. Indicates that the given column is part of the group definition. Multiple keys can be specified. If you are using partitioning with cliprows, make sure you are using a hash operator with the same key values. That is, the cliprows keys and hash keys must be the same otherwise incorrect results will be returned.
	PROPERTY	which	“first” or “last”	Required property. Indicates that the given column is part of the group definition. Multiple keys can be specified.
	PROPERTY	count	number >= 1	Required property. Indicates the number of rows to clip.
	OUTPUT	name.v		Output dataset.
DIFF				
	INPUT	input_1.v		Input dataset 1.
	INPUT	input_2.v		Input dataset 2.

OPREATOR Type (attribute)	Sub-Tag Name	Property Name	Property Value	Description
	PROPERTY	key	column_name	The key field to perform the comparison. Can be multiple columns.
	PROPERTY	allvalues	'true' or 'false'	True – compares all the values between the datasets. False – Does not compare all values. If this property is 'false' then the 'VALUE' property must be set (default).
	PROPERTY	value	column_name	After the “key” property has been used to join datasets, the “value” property is used to determine differences among the records in the joined datasets. Must be present in both before and after schemas. Determines if the record is a copy or a delete. The fields are processed one by one in the order they are present in the record.
	PROPERTY	copycode	2	The code that is written to the first field of the output dataset. The default is 2 if it is a copy.
	PROPERTY	editcode	3	The code that is written to the first field of the output dataset. The default value is 3.
	PROPERTY	deletecode	1	The code that is written to the first field of the output dataset. The default for a delete is 1.
	PROPERTY	insertcode	0	The code that is written to the first field of the output dataset. The default for an insert is 0.
	PROPERTY	dropcopy	True	To drop a copy record from the output. The default is true.
	PROPERTY	dropedit	True	To drop an edit record from the output. The default is true.
	PROPERTY	dropdelete	True	To drop a delete record from the output. The default is true.
	PROPERTY	dropinsert	True	To drop an insert record from the output. The default is true.

OPREATOR Type (attribute)	Sub-Tag Name	Property Name	Property Value	Description
	PROPERTY	sortascending	True	The operator assumes that the records are sorted in ascending order by default; use this field to change the sort order.
	OUTPUT	name.v		Output dataset.
CHANGE CAPTURE				
	INPUT	original.v		Input dataset 1. This is the original dataset.
	INPUT	changed.v		Input dataset 2. This is the modified dataset.
	PROPERTY	allvalues	'true' or 'false'	True – compares all the values between the datasets. False – Does not compare all values. If this property is 'false' then the 'VALUE' property must be set (default).
	PROPERTY	key	column_name	Records that match key fields are considered to be the same when determining existence in one dataset versus the other. After the two records are matched via the keys basis the operator can determine if there are copies or edits. If a record exists in the original dataset but not the changed dataset then it is considered to be a delete. Likewise if a record exists in the changed dataset but not the original it is an insertion. There can be multiple instances of this property, allowing the use of composite keys.
	PROPERTY	value	column_name	This property indicates which fields to base the comparisons after records have been matched on key fields. When the given values match the records are considered to be copies. When the values differ the records are considered to be edits. There can be multiple instances of this property, allowing the use of composite values.

OPREATOR Type (attribute)	Sub-Tag Name	Property Name	Property Value	Description
	PROPERTY	dropcopy	“true” or “false”	Indicates whether records determined to be copies should be filtered out of the output stream. The default is true.
	PROPERTY	dropedit	“true” or “false”	Similar to dropcopy, but with regard to edits. The default is false.
	PROPERTY	dropdelete	“true” or “false”	Similar to dropedit, but with regard to deletes.
	PROPERTY	dropinsert	“true” or “false”	Similar to dropedit, but with regard to inserts.
	PROPERTY	copycode	0	The value to set the change code field to for records that are copies. The default is 0.
	PROPERTY	insertcode	1	Similar to copycode, but for inserts. The default is 1.
	PROPERTY	deletecode	2	Similar to copycode, but for deletes. The default is 2.
	PROPERTY	editcode	3	Similar to copycode, but for edits. The default is 3.
	PROPERTY	codefield	column_name	The field name to set the change code field to.
	PROPERTY	sortascending	“true” or “false”	A Boolean property to indicate whether the incoming records are sorted in ascending order (true) on the key fields, or in descending order (false). The default is true.
	OUTPUT	name.v		Output dataset name.
SWITCH				
	INPUT	input.v		Input dataset name.
	PROPERTY	switchfield	field_name	Fieldname to determine the switch.
	PROPERTY	casevalues	“value1 = 0, value2 = 1”	This property assigns the switch value base on a comma separated list of mappings from value to output dataset. Note: output datasets are numbered starting from 0 starting from first specified to the last. Note: string values must be enclosed in single quotes. (e.g. “value1='str0', value2='str1'”)

OPREATOR Type (attribute)	Sub-Tag Name	Property Name	Property Value	Description
	PROPERTY	discard	“value”	Value to be discarded or dropped.
	PROPERTY	ifnotfound	“allow”, “fail”, “ignore”	<p>This property determines what to do with the record if the casevalues are not found.</p> <p>Allow – continues to next record and keeps the record in the output dataset.</p> <p>Fail – halts the process (default).</p> <p>Ignore – ignores the record from the dataset and writes to the reject dataset.</p>
	OUTPUT	valid.v		The valid output dataset. Number of outputs should correspond to number of casevalues. E.g. “value1=0, value2=1” should have two outputs (or three if ‘discard’ is specified)
	OUTPUT	reject.v		The reject output dataset.

Tag usage examples

```
<OPERATOR type="copy">
  <INPUT name="input.v" />
  <OUTPUT name="copy1.v" />
  <OUTPUT name="copy2.v" />
</OPERATOR>
```

```
<OPERATOR type="switch">
  <PROPERTY name="switchfield" value="Emp_Age" />
  <PROPERTY name="casevalues" value="35=0, 36=1" />
  <PROPERTY name="discard" value="38" />
  <PROPERTY name="ifnotfound" value="allow" />
  <INPUT name="import1.v" />
  <OUTPUT name="ds1.v" />
  <OUTPUT name="ds2.v" />
  <OUTPUT name="default.v" />
</OPERATOR>
```

```
<OPERATOR type="compare">
  <PROPERTY name="key" value="NAME"/>
  <INPUT name="import1.v"/>
  <INPUT name="import2.v"/>
  <OUTPUT name="compare.v"/>
</OPERATOR>
```

```
<OPERATOR type="changecapture">
  <PROPERTY name="key" value="emp_age" />
  <PROPERTY name="value" value="emp_name" />
  <PROPERTY name="codefield" value="change_code" />
  <PROPERTY name="copycode" value="0" />
  <PROPERTY name="editcode" value="3" />
  <PROPERTY name="deletecode" value="2" />
  <PROPERTY name="insertcode" value="1" />
  <PROPERTY name="dropcopy" value="false" />
  <PROPERTY name="dropedit" value="true" />
  <PROPERTY name="dropdelete" value="true" />
  <PROPERTY name="dropinsert" value="true" />
  <PROPERTY name="allvalues" value="true" />
  <PROPERTY name="sortascending" value="false" />
  <INPUT name="import1.v" />
```

```
<INPUT    name="import2.v" />
<OUTPUT   name="changecapture.v" />
</OPERATOR>

<OPERATOR type="cliprows">
  <PROPERTY name="key" value="LOC"/>
  <PROPERTY name="which" value="first"/>
  <PROPERTY name="count" value="2"/>
  <INPUT name="import1.v"/>
  <OUTPUT name="cliprows.v"/>
</OPERATOR>

<OPERATOR type="diff">
  <PROPERTY name="key" value="emp_name" />
  <PROPERTY name="allvalues" value="true" />
  <INPUT name="import1.v" />
  <INPUT name="import2.v" />
  <OUTPUT name="diff.v" />
</OPERATOR>
```

Appendix A – Default Conversions

These are the default conversions for use by the [CONVERT](#) operator.

from UINT8

Conversion Name	Description
default	Converts to INT8 from UINT8.
default	Converts to UINT16 from UINT8.
default	Converts to INT16 from UINT8.
default	Converts to UINT32 from UINT8.
default	Converts to INT32 from UINT8.
default	Converts to UINT64 from UINT8.
default	Converts to INT64 from UINT8.
default	Converts to FLOAT from UINT8.
default	Converts to DFLOAT from UINT8.

from INT8

Conversion Name	Description
default	Converts to UINT8 from INT8.
default	Converts to UINT16 from INT8.
default	Converts to INT16 from INT8.
default	Converts to UINT32 from INT8.
default	Converts to INT32 from INT8.
default	Converts to UINT64 from INT8.
default	Converts to INT64 from INT8.
default	Converts to FLOAT from INT8.
default	Converts to DFLOAT from INT8.

from UINT16

Conversion Name	Description
default	Converts to UINT8 from UINT16.
default	Converts to INT8 from UINT16.
default	Converts to INT16 from UINT16.
default	Converts to UINT32 from UINT16.
default	Converts to INT32 from UINT16.
default	Converts to UINT64 from UINT16.
default	Converts to INT64 from UINT16.
default	Converts to FLOAT from UINT16.
default	Converts to DFLOAT from UINT16.

from INT16

Conversion Name	Description
default	Converts to UINT8 from INT16.
default	Converts to INT8 from INT16.
default	Converts to UINT16 from INT16.
default	Converts to UINT32 from INT16.
default	Converts to INT32 from INT16.
default	Converts to UINT64 from INT16.
default	Converts to INT64 from INT16.
default	Converts to FLOAT from INT16.
default	Converts to DFLOAT from INT16.

from UINT32

Conversion Name	Description
default	Converts to UINT8 from UINT32.
default	Converts to INT8 from UINT32.
default	Converts to UINT16 from UINT32.
default	Converts to INT16 from UINT32.
default	Converts to INT32 from UINT32.
default	Converts to UINT64 from UINT32.
default	Converts to INT64 from UINT32.
default	Converts to FLOAT from UINT32.
default	Converts to DFLOAT from UINT32.

from INT32

Conversion Name	Description
default	Converts to UINT8 from INT32.
default	Converts to INT8 from INT32.
default	Converts to UINT16 from INT32.
default	Converts to INT16 from INT32.
default	Converts to UINT32 from INT32.
default	Converts to UINT64 from INT32.
default	Converts to INT64 from INT32.
default	Converts to FLOAT from INT32.
default	Converts to DFLOAT from INT32.

from UINT64

Conversion Name	Description
default	Converts to UINT8 from UINT64.
default	Converts to INT8 from UINT64.
default	Converts to UINT16 from UINT64.
default	Converts to INT16 from UINT64.
default	Converts to UINT32 from UINT64.
default	Converts to INT32 from UINT64.
default	Converts to INT64 from UINT64.
default	Converts to FLOAT from UINT64.
default	Converts to DFLOAT from UINT64.

from INT64

Conversion Name	Description
default	Converts to UINT8 from INT64.
default	Converts to INT8 from INT64.
default	Converts to UINT16 from INT64.
default	Converts to INT16 from INT64.
default	Converts to UINT32 from INT64.
default	Converts to INT32 from INT64.
default	Converts to UINT64 from INT64.
default	Converts to FLOAT from INT64.
default	Converts to DFLOAT from INT64.

from SFLOAT

Conversion Name	Description
default	Converts to UINT8 from SFLOAT.
default	Converts to INT8 from SFLOAT.
default	Converts to UINT16 from SFLOAT.
default	Converts to INT16 from SFLOAT.
default	Converts to UINT32 from SFLOAT.
default	Converts to INT32 from SFLOAT.
default	Converts to UINT64 from SFLOAT.
default	Converts to INT64 from SFLOAT.

Note: Conversions to integer types will truncate decimal values.

from DFLOAT

Conversion Name	Description
default	Converts to UINT8 from DFLOAT.
default	Converts to INT8 from DFLOAT.
default	Converts to UINT16 from DFLOAT.
default	Converts to INT16 from DFLOAT.
default	Converts to UINT32 from DFLOAT.
default	Converts to INT32 from DFLOAT.
default	Converts to UINT64 from DFLOAT.
default	Converts to INT64 from DFLOAT.

Note: Conversions to integer types will truncate decimal values.

Appendix B – Troubleshooting Guide

This Troubleshooting Guide has been developed to provide RETL installation, development and operation suggestions for common support issues. The suggested resolutions are in response to product and documentation feedback from RETL users to the RETL product team.

When trying to run rfx I get this error: ksh: rfx: cannot execute.

RETL is not installed or configured properly. Try running `verify_retl` from the command line to get more information about the problem. Reinstalling RETL may also resolve the problem.

Are there any suggestions for how best to develop and debug flows?

Yes, there are several important steps you should take when developing and debugging to keep you on the right track.

- 1 Do not optimize until you have a working flow. Specifically, set `numpartitions` to 1. Do not use the HASH operator. When your initial development is complete then worry about tuning for performance.
- 2 When building new flows, start small and work your way up. Add another operator only after you've tested the smaller flow. Back up your work often so that you can look at the diffs between flows in order to narrow problems to smaller segments.
- 3 As you are coding, copy and paste from examples that you know work to avoid syntax/xml errors if you are using a text editor.
- 4 When you run into problems, try breaking up your flows. Insert debugs and/or exports to show that your flow is working to a certain point (think binary search here). Move these operators further down the flow until you figure out what is causing it to break. A feature that has been added since version 10.3 is the ability of RFX to print schemafiles for each dataset connecting operators (by adding `'-sSCHEMAFILE'` to the command line options). This greatly aids when breaking up and debugging flows, by printing out each input/output schema in schemafile format. See the section [RFX Command line options](#) for more information about the `'-sSCHEMAFILE'` option.
- 5 As of release 10.3, you can look at the logfile to see when operators start, stop and how many records are flowing through them. Turn on more details by specifying a higher "level" in the LOGGER section of the configuration (see [Configuration](#) section for more details).

When running rfx I get the following error: Error connecting to the database().

You've probably typed an invalid database name, userid, or password. Verify that these parameters are correct (See steps 1-4 of [Appendix B – Database Troubleshooting](#)) and try again.

How do I tell what commands are being sent to the database?

Previous versions of rfx streamed database commands to the console by default. To see these commands starting from version 1.7, you should ensure that the environment variable “RFX_SHOW_SQL” is defined within your environment. Assuming that you are using ksh, you can do this by putting the following statement into your .profile or .kshrc, for example:

```
export RFX_SHOW_SQL=1
```

I got an error message about operator “sort:3”. How do I figure out which operator “sort:3” is?

RFX names operators internally based upon the type and their position within the specified XML flow. Assuming that numpartitions is set to 1, sort:3 is the fourth sort operator in the XML flow (RFX starts counting at 0).

This becomes a bit more complex if you are using partitioning (numpartitions>1). In short, partitioning splits data and creates parallel data streams within the flow. In effect this multiplies the number of operators being used depending upon the position within the flow and other factors.

There are two ways to determine what operator RFX is referring to in this case. The easiest way is to set numpartitions to 1 and count the operators of that type within the flow. If you cannot do this, then run the flow again except specify the “--graphviz-files” option. This generates two “.dot” files which contain the flow before and after partitioning. In order to view these you need to download a copy of “dotty” which is included with the graphviz package available from AT&T Bell Labs: (<http://www.research.att.com/sw/tools/graphviz/download.html>).

I’ve hashed and sorted my data, but for some reason my output data is not sorted. What is wrong?

Your partitioning is probably set to a value greater than 1. Hashing your data allows RFX to break up your data and parallelize your flow into separate data streams. Later in the flow RFX will rejoin these separate data streams. By default RFX will do this by using the COLLECT or FUNNEL operator. However, these operators do not keep the dataset in sorted order, hence your unsorted output. You can correct this problem by explicitly using a SORTCOLLECT to rejoin the data whenever you are rejoining sorted data.

This problem is also avoided by not partitioning (set partitioning to 1 and/or don’t specify a hash). As always, we recommend that you keep flows as simple as possible until or unless you need the performance boost that partitioning can give you.

I’m using sortcollect (or sortfunnel), but my data is not sorted! What is wrong?

Sort funnel performs a merge sort. It requires sorted input and can merge multiple inputs maintaining sorted order. It cannot perform a full sort of the data. You should use sort to do a full sort of a single data stream. Sortfunnel can be used to merge two data sources that are already sorted on the same keys – the result is a single data stream sorted on the same key.

I am missing fields within my flow. Where did they go?

Often the cause of this problem is that a schema file is incorrect (search for missing quotes, extra quotes) or the database schema is not what you expected. If your flow is not working correctly, take a look at the schemas that are output to stdout when RFX first starts up (specify the “-s” option if necessary to make RFX output the schemas). Look carefully at the schemas displayed for each operator within the flow. Make sure that these display ALL of the fields that you expect to see for this part of the flow. If you are missing fields or fields are of the wrong type, trace backwards to where the schema originates to try and find the source of the problem.

If you are using partitioning and are seeing operators that you do not expect, refer to [I got an error message about operator “sort:3”. How do I figure out which operator “sort:3” is?](#) This section helps you understand exactly what operators RFX is seeing so that you can more easily find the source of your problem.

How do I filter values from two different tables?

Currently filter assumes that all values required for the filter are in one record. This makes it a bit more difficult to compare values from multiple tables. The way to handle this is to JOIN the two tables and then filter the values after the join.

How do I filter out a set of dynamic values from a data stream?

How do I filter out a set of values? For example – I want to remove any records whose “FIRST_NAME” column does not have a value in the set {Joe, Susan, Mary} and keep all the rest.

This is easily done with RFX using the LOOKUP operator. Simply use the filter set as the key for the lookup. Import a flat file and or table with a single column describing the values to filter – FIRST_NAME = {Joe, Susan, Mary} and use that as the input for the lookup table of the lookup. Any matches are discarded and any misses are processed.

So the actual lookup would look something like this:

```
<OPERATOR type="lookup">
  <PROPERTY name="tablekeys" value="FIRST_NAME"/>
  <PROPERTY name="ifnotfound" value="continue"/>
  <INPUT name="records_to_filter.v"/>
  <INPUT name="set_names_to_drop.v"/>
  <OUTPUT name="records_in_set.v"/>
  <OUTPUT name="records_not_in_set.v"/>
</OPERATOR>
```

How do I translate from database types (e.g. NUMBER(12,4)) to RFX types?

Numbers work differently within RFX than they do within databases. This can cause a good deal of confusion. In short, RFX does not currently support arbitrary precision math and therefore has a limited amount of precision to deal with.

Specifically, here is the size and precision that each type has available:

RFX Type	Max Size	Max Precision	Validation/Numeric Range
DFLOAT	25	15	Min= -2.2250738585072014E-308 Max= 1.7976931348623157E+308
SFLOAT	25	6	Min=-1.17549435E-38 Max=3.40282347e+38
INT8	4	4	Min=-128 Max=127
INT16	6	6	Min=-32768 Max=32767
INT32	11	11	Max=2147483647 Min=-2147483648
INT64	20	20	Min=-9223372036854775808 Max=9223372036854775807
UINT8	3	3	Min=0 Max=255
UINT16	5	5	Min=0 Max=65535
UINT32	10	10	Min=0 Max=4294967295U
UINT64	20	20	Min=0 Max=18446744073709551615
DATE	8	8	Is specified in MMDDYYYY where: MM=01-12 DD=01-31 YYYY=0000-9999
TIME	8	8	Is specified in HH24MISS format where: HH24=00-23 MI=00-59 SS=00-59

RFX Type	Max Size	Max Precision	Validation/Numeric Range
TIMESTAMP	16	16	Is specified in YYYYMMDDHH24MISS format where: MM=01-12 DD=01-31 YYYY=0000-9999 HH24=00-23 MI=00-59 SS=00-59

Note the “Max Precision” column above. For integral types the precision is roughly equivalent to the size (the caveat being the min and max values in the table); however for floating point types (sfloat and dfloat) the precision indicates how many total digits to the left of the decimal point (assuming that the float is written in scientific form) you can look at before rounding errors are encountered.

If you are determining what types to use from an imported file, we recommend that you use the biggest numeric type you can (i.e. int64, uint64 or dfloat) to ensure that data is properly preserved and the flow works for as many different sets of data as possible. If you know your data very well and are sure that you can use a small type, you may get a bit of a performance boost by making this a restriction. RFX warns you on the IMPORT if your data cannot be represented by the type that you’ve chosen.

Is there a common set of Properties for all database operators?

Originally, RFX was developed to try and stay consistent with each of the database vendor’s terminology. This, however, made it very difficult to write code that was portable between the different databases and to understand how to write flows for different databases. Starting in release 10.2 the following common properties have been added to each of the database operators:

- userid
- password
- tablename

Over time we will attempt to merge the database operators so that RFX is database independent without the use of shell variables.

In my query, I am explicitly selecting the timestamp field as 'YYYYMMDDHH24MISS', but the data in the output file reads "invalid date". What am I doing wrong?

Currently RFX cannot read DATE, TIME and TIMESTAMP types directly out of the database. Because there is no conversion from string to these fields if you must access these fields as DATE, TIME and/or TIMESTAMP you will have to export your data to a file and then import it as a date field.

When attempting an orawrite I get the following error: SQL*Loader-951: Error calling once/load initialization

When you use ORAWRITE operator with the “method” property set to “direct,” you may get the following error message in your SQL*Loader log file:

```
SQL*Loader-951: Error calling once/load initialization
ORA-26028: index name.name initially in unusable state
```

It is because SQL*Loader cannot maintain the index which is in IU state prior to the beginning of a direct path load. Fix this problem by recreating the table index.

[IBM][CLI Driver] SQL0290N Table space access is not allowed.

You are using a DB2WRITE but the table you are loading to is not setup for multiple nodes. See Direct mode loading with db2write to correct this problem.

[IBM][CLI Driver][DB2/SUN] SQL0911N The current transaction has been rolled back because of a deadlock or timeout. Reason code "2". SQLSTATE=40001

This error can occur if you have a deadlock condition in your flows. Specifically, check for cases where the same table is accessed/locked for writing by multiple operators within a flow or a set of flows that are running concurrently.

In the case of deadlocks, you may want to create an event monitor for deadlocks to gather more information for diagnosis. You might also try increasing the number of “maxlocks” to avoid lock escalation, which can often result in a deadlock scenario.

[IBM][CLI Driver] SQL1224N A database agent could not be started to service a request, or was terminated as a result of a database system shutdown or a force command.

See [DB2 on AIX](#) to resolve this problem.

How do I request help when all else fails?

Contact support@retек.com. When requesting help with a flow follow these guidelines to get a more rapid response:

- 1 Minimize the scope of the problem. Submit the minimal flow with the minimal set of data and minimal schema that still reproduces the problem. This helps to ensure that the support team does not waste time trying to understand a long complicated flow and/or the data involved – allowing us to focus on the true problem.
- 2 If you have a database operator, (e.g. ORAREAD, ORAWRITE) separate the data from the database. Usually the database is not the problem; therefore removing the database operator from the equation makes our job easier. Replace the DB operator (e.g. ORAREAD, ORAWRITE) with an IMPORT or EXPORT operator. Use the exact same schema as is in the database. Extract a sample set of data into a flat file for the IMPORT operator. This should allow the support team to reproduce your problem here and debug it if necessary. This drastically reduces the amount of time it would take us to look into the problem otherwise.

- 3 If removing the database operator removes the problem then look very carefully to make sure that there is not a syntax error in the database operator. If you cannot find anything there, look at the IMPORT schema and make sure that it matches the database schema exactly (including null fields, etc). Finally, look at the flat file that the IMPORT operator is using. Make sure that you are using the correct delimiter, that the delimiter is not within the data and that the data is valid. Try setting the “rejectfile” property to see if there are any rejected records. If all this looks good then there may be a problem with the DB operator. Contact us and let us know what you’ve found.
- 4 Submit the flow and all data files associated with the flow so that the support team can run “rfx -f <yourflowname>” to reproduce the problem along with the log file from “verify_retl” so they can reproduce your environment.

I’ve upgraded and now I get WARNINGS when I never did before! What’s wrong!?

Each version of RETL brings better identification of errors and what might have been overlooked previously is now being caught. “WARNING” messages are generated if the property names and/or values don’t match the spelling/case noted in the Programmer’s Guide. It is very important to run the latest version of RETL and correct the warnings since they indicate that parameters are incorrect. If incorrect, they can produce unexpected results and/or corrupt data. In the future, RETL will stop processing and display error messages rather than just providing warnings to stop the flow until the problem is fixed. Warnings are being used as an intermediate step to minimize the impact to existing product.

Appendix C – Database configuration and Troubleshooting Guide

Since RETL database operators work with database servers and utilities, validating RETL requires some background in database setup and administration. Specifically this involves database setup, RETL database login id privileges, and database connectivity, etc.

RETL Database configuration and maintenance notes

RETL uses very specific tools in order to access the different databases. RETL developers should be sure that their Database Administrator is aware of what RETL does, and how the database needs to be setup to support RETL activities. Below are notes particular to certain databases and platforms.

Debugging database ETL utilities

The DBWRITE operators use the database specific import/export utilities. If you run into problems specific to the database and/or database operators, take a look at the log files and/or control files generated by the database operators (see [How do I tell what commands are being sent to the database?](#)). You may be able to better diagnose these problems by checking the utility's limitations, restrictions, environment, and privileges to see if there is a misconfiguration either with the database or within the rfx flow.

Database semaphore problems

Semaphores from database utilities and ODBC instances invoked by rfx may not be properly cleaned up if an rfx process or job is killed from Unix. In order to find and clean up semaphores use “`ipcs -s`” and “`ipcrm -s`” respectively.

Runaway loader processes

Sometimes when rfx is killed some ancillary database utilities are left running. These can be killed via the normal Unix kill command.

For Oracle the executable is called “`sqlldr`”.

For DB2 the executable is called “`db2atldr`”.

TeraData has several executables: “`mload`”, “`fastload`”, and “`fexp`”.

Troubleshooting RETL with your database

The following RETL/ database setup validation steps will help you work with your DBA and System Administrator to verify and troubleshoot the RETL/database installation.

Note below that we include commands that should be executed from the command line. These are written in `Courier` font. Additionally, variables such as machine names and IP addresses that should be replaced by values particular to your environment are surrounded in `<>` like this: `<variable name>`.

- 1 Run verify_retl.

If you have not already done so run the verify_retl script and correct any problems as directed by the script. When this is running properly proceed to step 2.

- 2 Verify that your databases are setup properly.

For all databases go through [RETL Database Configuration Notes](#) to make sure that the database is setup properly.

- 3 Verify database connectivity

Check connection between rfx local machine to remote database machine if the database and rfx are not in the same machine. We recommend that RETL is located on the database machine for better performance for Oracle and DB2 – Teradata is always located on a remote machine.

```
ping <database machine name>
```

If this fails, try pinging the IP address directly:

```
ping <database machine IP address>
```

If this works then your DNS isn't set up properly. Contact your Network Administrator to fix the problem by adding the IP address to the DNS.

If this second ping command fails then you need to contact your Network Administrator to determine why you cannot contact the machine. Until this problem is resolved RETL will not work.

- 4 Check database server connectivity.

For Oracle:

```
tnsping <Oracle Server Name>
```

If this fails contact to your DBA for TNS name setup.

5 Verify database login id/password.

Login the database by using the appropriate database utilities.

For Oracle:

```
sqlplus userid/password@Oracle_database_server
```

For DB2:

```
db2 connect to database_name user id using password
```

For Teradata:

```
Bteq database_server_name
logon
user id
password
```

Contact to your DBA if this step fails – your userid/password is not setup correctly.

6 Check database user id privileges.

Contact your DBA to ensure that the RETL user has privileges to: select, insert, update, create table, etc. Since RETL database operators invoke database utilities to extract and load (see [Chapter 5 Database Operators](#) for details), your RETL DB user needs privileges to meet all of the utilities requirements.

These are the privileges that each of the operators require:

Operators	Privilege
ORAREAD, DB2READ, TERAFERREAD	select
ORAWRITE, DB2WRITE, TERAWRITE	select, insert, update, create table, drop table, load

We recommend setting up the RETL/database login id with create/drop table privileges during RETL/database setup phase so that we can run the RETL/database test flows to verify that the database is setup properly for RETL.

7 Run RETL/database testing scripts.

Note these scripts require that the retl userid has full privileges to run. If you don't have the appropriate privileges to change tables you can still run the read scripts to verify that you can read from the database without problems go to step 10.

For Oracle:

```
$RFX_HOME/samples/oracle.ksh <database name> <userid>
<password>
```

For DB2:

```
$RFX_HOME/samples/db2.ksh <database name> <userid>
<password>
```

For Teradata:

```
$RFX_HOME/samples/tera.ksh <database name> <userid>
<password>
```

These scripts will:

- Create a "RETL_test" table with two columns and two rows on your database owned by the given userid.
- Read the two rows from the database and verify that the rows contain the correct information.
- Compare the results from read and verify what was supposed to be written.

In short, this test verifies both RETL read operator and RETL write operator appropriate to the database type.

If the scripts are working properly you see something like the following:

```
Testing a write to etlsun9i
Reading data back out of etlsun9i
Comparing data received from etlsun9i and expected
output...
Test Passed!
```

If both tests succeed - Congratulations your database seems to be properly configured! Skip the following steps.

If the scripts are not working properly you will see the following:

```
Testing a write to etlsun9i
RFX Unexpected Error: Operator.cpp:385: 'Operator: orawrite
is not a registered operator'
Reading data back out of etlsun9i
RFX Unexpected Error: Operator.cpp:385: 'Operator: oraread
is not a registered operator'
Comparing data received from etlsun9i and expected
output...
diff: oraread.out: No such file or directory
Changes were detected! Test failed!
```

If either test fails you need to move onto the following steps to try and diagnose the problem. If the DB write operator passed but the read operator did not, move onto step 9. If both failed then move onto step 8.

8 Debugging a DBWRITE failure.

This step verifies that the database write operator is working properly.

For Oracle:

```
orawrite.ksh <database_name> <userid> <password>
```

For DB2:

```
db2write.ksh <database_name> <userid> <password>
```

For Teradata:

```
terawrite.ksh <database_name> <userid> <password>
```

This flow works if the last line of output shows "Flow ran successfully". Go to step 9.

Here are some common failures and their causes:

'Operator: db2write is not a registered operator.'

RETL does not recognize the database operator (see [When you try to run rfx you get an error like: 'Operator: db2write is not a registered operator.'](#)). First double-check that you are using the correct shell script for this test – this error will happen if you use the wrong script for your binary. If you are using the correct script this error means that you've installed the wrong RETL for the database you are trying to access – this version of RETL does not support the operator necessary for accessing the database you are trying to read from. You need to reinstall RETL selecting the appropriate database for your environment.

Note: RETL binaries currently only support 1 database type each. Multiple binaries would have to be installed in order to access different types of databases.

'Error Connecting to the database()'

You've probably typed an invalid database name, userid, or password (see [When running rfx I get the following error: 'Error Connecting to the database\(\)'](#)). Verify that these parameters are correct (See step 4 above) and try again.

If you still cannot find the problems you can try running step 10 on a table that you know already exists.

9 Debugging a DBREAD failure.

This step will verify that the database read operator is working properly.

For Oracle:

```
oraread.ksh <database name> <userid> <password>
```

For DB2

```
db2read.ksh <database name> <userid> <password>
```

For Teradata

```
teraferread.ksh <database name> <userid> <password>
```

If the last line of output shows “Flow ran successfully” your RETL/database setup is working for reads – Congratulations! You can run step 10 if you’d like to try extracting data from your own tables.

If it fails there are several possible reasons (generally the same as those for the write operator) – here are some common errors:

```
'Operator: db2read is not a registered operator.'
```

RETL does not recognize the database operator (see [When you try to run rfx you get an error like: 'Operator: db2write is not a registered operator.'](#)). First double-check that you are using the correct shell script for this test. This error happens if you use the wrong script for your binary. If you are using the correct script this error means that you’ve installed the wrong RETL for the database you are trying to access. This version of RETL does not support the operator necessary for accessing the database you are trying to read from. You need to reinstall RETL selecting the appropriate database for your environment.

Note: RETL binaries currently only support 1 database type each. Multiple binaries would have to be installed in order to access different types of databases.

```
'Error Connecting to the database()'
```

You’ve probably typed an invalid database name, userid, or password (see [When running rfx I get the following error: 'Error Connecting to the database\(\)'](#)). Verify that these parameters are correct (See step 4 above) and try again.

If you are still running into problems and there are valid tables that you know work, try step 10. Otherwise review the [RETL Database Configuration Notes](#), to verify that everything is set up correctly and try again.

10 Running the DBREAD script against user tables.

The database read scripts could be used to access any table to which you have read privileges by simply specifying the table name as the last parameter.

For Oracle:

```
oraread.ksh <database> <userid> <password> <table>
```

For DB2:

```
db2read.ksh <database> <userid> <password> <table>
```

For Teradata:

```
teraferread.ksh <database> <userid> <password> <table>
```

If the last line of output shows “Flow ran successfully” your RETL/database setup is working for reads on this table.

If you still cannot find out the problems, contact to Retek Support (support@rettek.com).

Appendix D – FAQs

Does RETL call stored procedures?

RETL can call stored procedures only within the ORAWRITE operator via the sp_prequery and sp_postquery, which run before and after the ORAWRITE operation respectively. These stored procedures can take static variables (not data from the flow) as parameters. We anticipate expanding on this feature in the future to allow lookups based upon flow data and support for other database operators.

Can RETL handle text translations (e.g. between EBSDIC and ASCII)?

Currently RETL does not do textual translation of this type.

Can RETL handle data translations (e.g. between numbers and strings, etc)?

Data translations between different fields can be done via the LOOKUP and JOIN operators.

Are clients able to obtain RETL performance metrics on RETL?

Generally clients are interested in how a particular flow that use RETL runs – rather than how RETL itself performs at a fundamental level. These are generally handled on a case-by-case basis for the different product groups since flows are very different from product to product and the environment differs depending hardware and configuration. Contact your product group to determine if they have benchmarking number specific to your group. The RETL group does benchmark internal performance results and these are made available via the Product Enhancement Review Board. Contact your product group for inclusion to this board.

Is it possible to do joins from 2 different databases?

Yes. This is generally done via two DBREAD operators and then a JOIN operator.

What error handling capabilities does RETL have?

There are many other areas where RETL does error handling and this capability has been expanding.

Error Handling – flow related problems. These are problems that an RETL flow developer might run into while developing flows using RETL. There are many different areas that RETL detects – because these are generally found only during development RETL usually exits with an error message describing one of the scenarios below:

- Schemas: mismatched input schemas (e.g. for FUNNEL), invalid schema specified (e.g. record length does not equal sum of field lengths).
- Mismatched datasets – RETL enforces 1-to-1 correspondence between inputs and outputs.
- Validation of operators, properties and property values.

Data related problems. These are found after the flow is parsed and execution begins. In these cases invalid or non-conforming data may be siphoned into a separate file for later processing:

- Improperly formatted fields via the IMPORT operator (invalid types, lengths, etc).
- Improperly formatted records via the IMPORT operator (missing fields, etc).
- Invalid schemas.

Additionally, flow developers can insert data validation to verify that various database constraints are upheld via a combination of LOOKUP, JOIN and FILTER operators.

What temp files does RETL create and how much space will they take up?

RETL generates temporary files dynamically in order to sort and store intermediate data. These files are generally prefixed with "rfx", but this is not always the case. Therefore, separate rfx files into their own tmp (e.g. /tmp/rfx) directory so that they can be easily purged on a regular basis (as per the Programmer's Guide). With the introduction of RETL 11.1, RETL will not write to a file before performing an external sort. Streams are now used to do in-place sorting, so the disk space required should be much less than what was required for 10.x versions.

How much space rfx will consume depends upon the complexity of the flows and how large the source system is. A good starting point is twice the size of the data being manipulated. A more conservative number is 3 times the size of the data being moved. Many people start with 10GB and move up from there if needed.

Note: It is recommended that system administrators clean up temporary files in the RETL temporary directory on a regular basis.

How do I participate in defining RETL requirements and future direction?

The Product Enhancement Review Board (PERB) is the forum to assist Retek product strategy in defining future enhancements to RETL. If you are not part of the PERB, contact your Retek point person or team lead to inquire about joining.

Appendix E – RETL 11.x-specific F.A.Qs

Why re-write RETL if it's not broken?

There are a number of reasons why the decision was made. Perhaps the biggest reason was that a huge portion of RETL development resources are required to support the 26 binaries on 3 different platforms for RETL 10.x. The maintenance costs here justify a port such that only one RETL package/binary would be required. Additionally, there are numerous other reasons, such as synergy with other Retek applications, congruency with Retek skill sets as a whole, speed of operator development, etc. that have driven 11.1's development.

Will pre-11.1 versions of RETL still be supported?

Since RETL is a customer-driven product, support for pre-11.1 versions is still considered top priority. Team RETL has built mini-milestones around consulting with customers and giving support to those upgrading to 11.1. While pre-11.1 releases will be supported as long as it is necessary for customers to migrate to 11.1, support for pre-11.1 versions may be dropped at some point in the future. The general guideline is that all fixes will be made to 11.x versions. 10.x versions may not be patched if the 11.x functions offer or provide a more appropriate solution.

Since RETL has been re-written in Java, can I run RETL on other platforms that have a JRE?

See the Compatibility Matrix in the Release Notes for supported platforms. While running RETL on platforms other than these is not supported, it is technically feasible that the core framework and operators should work on any platform that has a JRE version 1.4 or higher. We would certainly like to hear from you when/if you have successfully deployed on other platforms, and if these types of requests happen with much frequency/urgency, Team RETL will take this into account when prioritizing efforts for platform proliferation in future releases. Note that additional platform support comes at much less a cost than with previous versions of RETL (10.x).

With the introduction of RETL 11.x, JDBC technology has been introduced as a mechanism for connecting and reading from/writing to databases. Does this mean I can connect to any database (e.g. Sybase, MySQL, Acumate, etc)?

See the Supportability Matrix in the Release Notes for supported databases. While running RETL against databases other than these is not supported, it is possible that 'snapping in' a JDBC-compliant driver by using the generic 'dbread'/'dbwrite' operators will work. Please contact customer support if you are attempting to use a JDBC driver for an unsupported database. Note that additional database support in 11.x releases come at much less a cost than previous versions of RETL (10.x).

RETL 11.x has been re-written in Java. Is there a performance impact in doing this?

Part of the reason RETL was re-written was to address architectural models that have been shown to positively impact performance. Initial volume testing has shown that in many cases RETL 11.1 is significantly faster than pre-11.1 versions. Moreover, performance requirements on 11.1 mandate that it come within 30% or better performance for the BETA release, within 15% in the 1st GA release, and meet pre-11.1 performance in the 2nd GA release.

What changes do I need to make to my flows in order for RETL 11.x to run them?

RETL 11.1 requirements specify that it must be backwardly-compatible in the XML flow interface. As a result, only minor changes will need to be made. Read this document in its entirety to assess the need for these changes.

What is the 'upgrade plan' for RETL 11.x?

The recommended upgrade plan is for product groups to start testing with RETL 11.1 as soon as possible. Once product groups determine that RETL 11.x is a feasible upgrade for customers, it is recommended that deployment to these customers be taken. A formal upgrade plan with timelines will be crafted for each interested party at some point in the near future.

Can I deploy RETL 11.x directly to my customers or in a production environment?

This recommendation should come from the product group whose product implements RETL. Only after each product that uses RETL is certified on RETL 11.x should a customer or production system receive the upgrade.

I have a backwards-compatibility problem or other bug with RETL 11.1. Where do I send my bug report?

Narrow down the problem as much as possible, including the flow, data, and a schema file in order to reproduce your problem. Then, please send everything needed to reproduce this problem along with a brief explanation to Retek customer support through an entry of the issue in the customer support ROCS system.

I have been getting warnings about sorting/sort order such as the following:

[<operator>]: Warning: mismatched sort order - <operator> specifies "ascending" sort order and for the first INPUT to <operator> records are in "descending". These should match - otherwise you may get unexpected results!

OR

[<operator>]: Warning: Input to <operator> does not seem to be sorted! Data should be sorted according to the proper keys or you may get unexpected results!

OR

Various other warning messages dealing with sort order or sort keys

How do I remove these warnings?

Certain operators require that incoming data be sorted. To remove these error messages, place a sort operator that sorts by the required keys in the required order, before the operator in question. If you know that your data is always going to be sorted according to a particular set of keys, then you can specify this in the schemafile (See the [schemafile documentation](#) for more details on this). This last feature should be used with care since if data turns out to not be in the presumed sorted order, certain operators may produce unexpected results.

Which operators require sorted input?

This document should be read in its entirety to assess the need for sorted input. However, the following is a list of operators that do currently require sorted input:

- innerjoin
- leftouterjoin
- rightouterjoin
- fullouterjoin
- sortfunnel
- removedup
- compare
- changecapture
- diff
- groupby (only if 'key' properties are specified)

I have been getting errors when RETL tries to connect to the database such as the following:

--- SQLException caught ---

```
java.sql.SQLException: Io exception: Connection
refused(DESCRIPTION=(TMP=)(VSNNUM=153092608)(ERR=12505)(ERROR_
STACK=(ERROR=(CODE=12505)(EMFI=4))))
```

```
Message: Io exception: Connection
refused(DESCRIPTION=(TMP=)(VSNNUM=153092608)(ERR=12505)(ERROR_
STACK=(ERROR=(CODE=12505)(EMFI=4))))
```

XOPEN SQL State: null

Database Vendor Driver/Source Error Code: 17002

The 'hostname' or 'port' of the database read/write operator may be incorrect or not specified, or the database is down/non-existent. Make sure the database instance is up and running and located on the hostname/port specified in the flow or rfx.conf. If you are using an oracle database, check tnsnames.ora or use tnsping to figure out the hostname/port.