

Oracle® Database Vault

Installation Guide

10g Release 2 (10.2) for Solaris Operating System (SPARC
64-Bit)

B31294-05

May 2010

Oracle Database Vault Installation Guide, 10g Release 2 (10.2) for Solaris Operating System (SPARC 64-Bit)
B31294-05

Copyright © 2006, 2010, Oracle and/or its affiliates. All rights reserved.

Primary Author: Sumit Jeloka, Prakash Jashnani, Tanaya Bhattacharjee

Contributing Author: Pat Huey

Contributors: Scott Gaetjen, Xiaofang Wang, Jack Brinson, Chi Ching Chui, Kamal Tbeileh, Trivikrama Samudrala, Madhu Velukur, Rahul Joshi

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this software or related documentation is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, the following notice is applicable:

U.S. GOVERNMENT RIGHTS Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, duplication, disclosure, modification, and adaptation shall be subject to the restrictions and license terms set forth in the applicable Government contract, and, to the extent applicable by the terms of the Government contract, the additional rights set forth in FAR 52.227-19, Commercial Computer Software License (December 2007). Oracle USA, Inc., 500 Oracle Parkway, Redwood City, CA 94065.

This software is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications which may create a risk of personal injury. If you use this software in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure the safe use of this software. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software in dangerous applications.

Oracle is a registered trademark of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners.

This software and documentation may provide access to or information on content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

Contents

Preface	v
----------------------	----------

Part I Oracle Database Vault Installation

1 Oracle Database Vault Installation Overview

Database Vault Installation Environment	1-1
Database Vault Accounts	1-1
Database Vault Owner	1-1
Database Vault Account Manager	1-2
Default Audit Policy and Initialization Parameters	1-2
Installation Considerations	1-2
Hardware and Software Certification	1-2
Multiple Oracle Homes	1-2

2 Installing Oracle Database Vault

Preinstallation and Installation Tasks	2-1
Become Familiar with the Features of Oracle Database Vault	2-2
Check the Hardware Requirements	2-2
Check the Operating System Requirements	2-3
Check Kernel Parameters	2-6
Check the Database Requirements	2-8
Install Oracle Enterprise Manager Console DB	2-8
Apply Oracle Database Release 10.2.0.5 Patch Set	2-9
Prepare a Backup Strategy	2-9
Disable Custom Profiles (If Any)	2-10
Verify That Oracle Clusterware Is Running (Oracle RAC Only)	2-11
Stop Existing Oracle Processes	2-11
Stop the Enterprise Manager Database Control Process	2-11
Stop the iSQL*Plus Process	2-11
Shut Down All Database Instances	2-11
Configure the Oracle User's Environment	2-12
Run Oracle Universal Installer to Install Oracle Database Vault	2-14
Postinstallation Tasks	2-16
Back Up the Database	2-17
Update Environment Variables After the Upgrade (UNIX Systems Only)	2-17

Change Passwords for Oracle-Supplied Accounts	2-17
Using SQL*Plus to Unlock Accounts and Reset Passwords	2-17
Disable Remote SYSDBA Connections (Optional)	2-18
Start the Database on Other Nodes (Oracle RAC Only)	2-19
Configure Oracle Database Vault on Oracle RAC Nodes (Oracle RAC Only)	2-19
Set the Timeout Value for DVA (Optional)	2-20
Manually Deploy Oracle Database Vault Administrator (Special Cases)	2-20
Deploying Database Vault Administrator to a Standalone OC4J Container	2-20
Deploying Database Vault Administrator to the Database Console OC4J Container...	2-22
Removing Oracle Database Vault	2-23
Step 1: Deconfigure Oracle Database Vault	2-23
Step 2: Deinstall Oracle Database Vault.....	2-24

Part II Appendixes

A How to Stop Processes in an Existing Oracle Real Application Clusters Database

B Using Response Files

How Response Files Work	B-1
General Procedure for Using Response Files	B-2
Installing Database Vault Using a Response File	B-2
Prepare the Response File	B-2
Run Oracle Universal Installer Using the Response File.....	B-4
Troubleshooting Silent Mode Installation	B-4

C Running DVCA After Creating a Database Vault Database

D Upgrading from a Previous Version of Database Vault

Upgrading from a 10.2.0.x Version	D-1
---	-----

E Database Listener Security Recommendations

Security Checklist for the Database Listener.....	E-1
---	-----

F Initialization Parameters

G Enabling Oracle Database Vault Administrator Accessibility

Enabling Oracle Database Vault Administrator Accessibility Mode	G-1
Providing Textual Descriptions of Database Vault Administrator Charts.....	G-2

Index

Preface

The Oracle Database Vault Installation Guide explains how to prepare for, install, and configure Oracle Database Vault with specific instructions for the operating system and Oracle software technology components that Database Vault requires.

Audience

This document is intended for Oracle DBAs as well as System Administrators who are involved in the installation of Oracle Database Vault and its related components.

Documentation Accessibility

Our goal is to make Oracle products, services, and supporting documentation accessible to all users, including users that are disabled. To that end, our documentation includes features that make information available to users of assistive technology. This documentation is available in HTML format, and contains markup to facilitate access by the disabled community. Accessibility standards will continue to evolve over time, and Oracle is actively engaged with other market-leading technology vendors to address technical obstacles so that our documentation can be accessible to all of our customers. For more information, visit the Oracle Accessibility Program Web site at <http://www.oracle.com/accessibility/>.

Accessibility of Code Examples in Documentation

Screen readers may not always correctly read the code examples in this document. The conventions for writing code require that closing braces should appear on an otherwise empty line; however, some screen readers may not always read a line of text that consists solely of a bracket or brace.

Accessibility of Links to External Web Sites in Documentation

This documentation may contain links to Web sites of other companies or organizations that Oracle does not own or control. Oracle neither evaluates nor makes any representations regarding the accessibility of these Web sites.

Access to Oracle Support

Oracle customers have access to electronic support through My Oracle Support. For information, visit <http://www.oracle.com/support/contact.html> or visit <http://www.oracle.com/accessibility/support.html> if you are hearing impaired.

Related Documents

For more information, refer to the following documents:

- *Oracle Database Vault Release Notes for Solaris Operating System (SPARC 64-Bit)*
- *Oracle Database Vault Administrator's Guide*
- *Oracle Database Installation Guide*
- *Oracle Database Oracle Clusterware and Oracle Real Application Clusters Installation Guide for Solaris Operating System*
- *Oracle Database Oracle Clusterware and Oracle Real Application Clusters Administration and Deployment Guide*

Conventions

The following text conventions are used in this document:

Convention	Meaning
boldface	Boldface type indicates graphical user interface elements associated with an action, or terms defined in text or the glossary.
<i>italic</i>	Italic type indicates book titles, emphasis, or placeholder variables for which you supply particular values.
<code>monospace</code>	Monospace type indicates commands within a paragraph, URLs, code in examples, text that appears on the screen, or text that you enter.

Part I

Oracle Database Vault Installation

Part I introduces you to Oracle Database Vault installation concepts, requirements, and steps. This part contains the following chapters:

- [Chapter 1, "Oracle Database Vault Installation Overview"](#)
- [Chapter 2, "Installing Oracle Database Vault"](#)

Oracle Database Vault Installation Overview

Oracle Database Vault enables you to secure business data in ways that were not possible before. Database Vault uses a multifactored and multilayered approach to implementing database security.

This chapter provides an overview of the Database Vault installation process. This chapter includes the following sections:

- [Database Vault Installation Environment](#)
- [Database Vault Accounts](#)
- [Installation Considerations](#)

Database Vault Installation Environment

Oracle Database Vault can be installed as an option to the following:

- Oracle Database 10g Release 2 (10.2.0.5) standalone installation
- Oracle Database 10g Release 2 (10.2.0.5) with Oracle Real Application Clusters (Oracle RAC)

Database Vault Accounts

Database Vault prompts for two accounts that you can create during installation. These are the Database Vault Owner and the Database Vault Account Manager accounts. You must supply an account name and password for the Database Vault Owner during installation. Creating a Database Vault Account Manager is optional.

Database Vault Owner

The Database Vault Owner account is granted the DV_OWNER role. This account can manage Database Vault roles and configuration.

The Database Vault Owner user name can be a minimum of 2, and a maximum of 30 characters long. The account password can be a minimum of 8, and a maximum of 30 characters.

The password that you choose for the Database Vault Owner account must be a secure one. The following password restrictions are enforced:

- The password must include at least one alphabet, one digit, and one nonalphanumeric character (symbol).
- The password cannot be the same as the account name.

- The password cannot contain any consecutive repeating characters.

Database Vault Account Manager

The Database Vault Account Manager is granted the DV_ACCTMGR role. This account is used to manage database user accounts. The Database Vault Account Manager is created to facilitate separation of duties. If you do not opt to create the Database Vault Account Manager account, then the DV_ACCTMGR role is granted to the Database Vault Owner account by default.

The Database Vault Account Manager user name can be a minimum of 2, and a maximum of 30 characters long. The account password can be a minimum of 8, and a maximum of 30 characters.

The same password restrictions that apply to Database Vault Owner are applicable to Database Vault Account Manager as well.

Default Audit Policy and Initialization Parameters

Oracle Database Vault installs a baseline database auditing policy. This policy covers the access control configuration information stored in Database Vault database tables, information stored in Oracle Catalog (rollback segments, tablespaces, and so on), the use of system privileges, and Oracle Label Security configuration.

See Also: *Oracle Database Vault Administrator's Guide* for more information on the database audit policy

When you install Oracle Database Vault, the security specific database initialization parameters are initialized with default values. These security specific initialization parameters are listed in [Appendix F](#)

Installation Considerations

This section contains information that you should consider before deciding how to install this product. It contains the following sections:

- [Hardware and Software Certification](#)
- [Multiple Oracle Homes](#)

Hardware and Software Certification

The platform-specific hardware and software requirements included in this installation guide were current at the time this guide was published. However, because new platforms and operating system software versions might be certified after this guide is published, review the certification matrix on the My Oracle Support (formerly OracleMetaLink) Web site for the most up-to-date list of certified hardware platforms and operating system versions. My Oracle Support is available at the following URL:

<https://support.oracle.com>

Multiple Oracle Homes

This product supports multiple Oracle homes. This means that you can install this release or previous releases of the software more than once on the same system, in different Oracle home directories.

Installing Oracle Database Vault

This chapter includes an overview of the major steps required to install Oracle Database Vault into an existing Oracle Database 10g Release 2 (10.2.0.5) database. These procedures transform an existing Oracle Database system (including associated applications) into an Oracle Database Vault system. Databases upgraded using the procedures described in this chapter can work almost in the same manner as in earlier releases and, optionally, can leverage new Oracle Database Vault functionality. For a list of changes that Database Vault makes, refer to [Appendix F, "Initialization Parameters"](#) and the *Oracle Database Vault Administrator's Guide*.

Note: In order to upgrade a pre-10g release 2 Oracle Database to Oracle Database Vault, you first need to upgrade the database to a 10g Release 2 (10.2.0.5) database.

See Also: *Oracle Database Upgrade Guide, 10g Release2 (10.2)* for information about upgrading your Oracle Database to Oracle Database 10g release 2.

This chapter covers the following topics:

- [Preinstallation and Installation Tasks](#)
- [Postinstallation Tasks](#)
- [Removing Oracle Database Vault](#)

Preinstallation and Installation Tasks

This section covers the following topics:

- [Become Familiar with the Features of Oracle Database Vault](#)
- [Check the Hardware Requirements](#)
- [Check the Operating System Requirements](#)
- [Check Kernel Parameters](#)
- [Check the Database Requirements](#)
- [Prepare a Backup Strategy](#)
- [Disable Custom Profiles \(If Any\)](#)
- [Verify That Oracle Clusterware Is Running \(Oracle RAC Only\)](#)
- [Stop Existing Oracle Processes](#)

- [Configure the Oracle User's Environment](#)
- [Run Oracle Universal Installer to Install Oracle Database Vault](#)

Become Familiar with the Features of Oracle Database Vault

Before you plan the upgrade process, become familiar with the features of Oracle Database Vault. The *Oracle Database Vault Administrator's Guide* discusses the basic features of Oracle Database Vault.

Check the Hardware Requirements

The system must meet the following minimum hardware requirements:

- At least 1024 MB of available physical RAM
- The following table gives the relationship between the available RAM and the required swap space.

Available RAM	Swap Space Required
Between 1024 MB and 2048 MB	1.5 times the size of RAM
Between 2049 MB and 8192 MB	Equal to the size of RAM
More than 8192 MB	0.75 times the size of RAM

- 400 MB of disk space in the `/tmp` directory
- Between 1.5 GB and 3.5 GB of disk space for the Oracle software, depending on the installation type
- 1.2 GB of disk space for a preconfigured database that uses file system storage (optional)

Note: The disk space requirement for databases that use Automatic Storage Management or raw device storage is described later in this chapter.

Additional disk space, either on a file system or in an Automatic Storage Management disk group, is required for the flash recovery area if you choose to configure automated backups.

To ensure that the system meets these requirements:

1. To determine the physical RAM size, enter the following command:

```
# /usr/sbin/prtconf | grep "Memory size"
```

If the size of the physical RAM installed in the system is less than the required size, then you must install more memory before continuing.

2. To determine the size of the configured swap space, enter the following command:

```
# /usr/sbin/swap -s
```

If necessary, refer to your operating system documentation for information about how to configure additional swap space.

3. To determine the amount of disk space available in the `/tmp` directory, enter the following command:

```
# df -k /tmp
# df -h /tmp (on Solaris 10)
```

If there is less than 400 MB of free disk space available in the /tmp directory, then complete one of the following steps:

- Delete unnecessary files from the /tmp directory to meet the disk space requirement.
 - Set the TMP and TMPDIR environment variables when setting the oracle user's environment (described later).
 - Extend the file system that contains the /tmp directory. If necessary, contact your system administrator for information about extending file systems.
4. To determine the amount of free disk space on the system, enter the following command:

```
# df -k
# df -h (on Solaris 10)
```

The following table shows the approximate disk space requirements for software files for each installation type:

Installation Type	Requirement for Software Files (GB)
Enterprise Edition	2.0
Standard Edition	1.5
Custom (maximum)	2.5

5. To determine whether the system architecture can run the software, enter the following command:

```
# /bin/isainfo -kv
```

Note: The following is the expected output of this command:

```
64-bit sparcv9 kernel modules
```

If you do not see the expected output, then you cannot install the software on this system.

Check the Operating System Requirements

Depending on the products that you intend to install, verify that the following software is installed on the system. The procedure following the table describes how to verify whether these requirements are addressed.

Note: Oracle Universal Installer performs checks on your system to verify that it meets the listed requirements. To ensure that these checks pass, verify the requirements before you start Oracle Universal Installer.

Item	Requirement
Operating system	One of the following 64-bit operating system versions: ■ Solaris 8 Update 7 or later ■ Solaris 9 Update 6 or later ■ Solaris 10 Note: The operating system requirements are the same as those for Oracle Database 10g release 2. If you already have Oracle Database 10g release 2 installed, then your system automatically meets these requirements.
Packages	SUNWarc SUNWbtool SUNWhea SUNWlibm SUNWlibms SUNWsprot SUNWtoo SUNWilof SUNWilcs SUNWi15cs SUNWxfnt SUNWsprox Note: You may also require additional font packages for Java, depending on your locale. Refer to the following Web site for more information: http://java.sun.com/j2se/1.4.2/font-requirements.html

To ensure that the system meets these requirements:

1. To determine which version of Solaris is installed, enter the following command:

```
# uname -r
5.9
```

In this example, the version shown is Solaris 9 (5.9). If necessary, refer to your operating system documentation for information about upgrading the operating system.

2. To determine whether the required packages are installed, enter a command similar to the following:

```
# pkginfo -i SUNWarc SUNWbtool SUNWhea SUNWlibm SUNWlibms SUNWsprot \
SUNWsprox SUNWtoo SUNWilof SUNWilcs SUNWi15cs SUNWxfnt
```

If a package is not installed, then install it. Refer to your operating system or software documentation for information about installing packages.

In addition, you need to verify that the following patches are installed on the system. The procedure following the table describes how to check these requirements.

Note: There may be more recent versions of the patches listed installed on the system. If a listed patch is not installed, then determine whether a more recent version is installed before installing the version listed.

Installation Type or Product	Requirement
All installations	Patches for Solaris 8: All of the patches included in the J2SE Patch Cluster for Solaris 8: 108528-23, SunOS 5.8: kernel update patch 108652-66, X11 6.4.1: Xsun patch 108773-18, SunOS 5.8: IIIM and X I/O Method patch 108921-16, CDE 1.4: dtwm patch 108940-53, Motif 1.2.7 and 2.1.1: Runtime lib. patch for Solaris 8 108987-13, SunOS 5.8: Patch for patchadd and patchrm 108989-02, /usr/kernel/sys/acctctl & /.../exactsys patch 108993-45, SunOS 5.8: LDAP2 client, libc, libthread and libnsl libraries patch 109147-24, SunOS 5.8: linker patch 110386-03, SunOS 5.8: RBAC Feature Patch 111023-02, SunOS 5.8: /kernel/fs/mntfs and ... sparcv9/mntfs 111111-03, SunOS 5.8: /usr/bin/nawk patch 111308-03, SunOS 5.8: /usr/lib/libmtmalloc.so.1 patch 111310-01, SunOS 5.8: /usr/lib/libdhcpagent.so.1 patch 112396-02, SunOS 5.8: /usr/bin/fgrep patch The following additional patches: 111721-04, SunOS 5.8: Math Library (libm) patch 112003-03, SunOS 5.8: Unable to load fontset ... iso-1 or iso-15 112138-01, SunOS 5.8: usr/bin/domainname patch
All installations	Patches for Solaris 9: 112233-11, SunOS 5.9: Kernel Patch 111722-04, SunOS 5.9: Math Library (libm) patch The following additional patches are required for Numa Systems: 115675-01, SunOS 5.9: liblgrp API 113471-08, SunOS 5.9: Miscellaneous SunOS Commands Patch 115675-01, SunOS 5.9: /usr/lib/liblgrp.so Patch

Note: The following patches are not required for silent installations:

- 108652-66, X11 6.4.1: Xsun patch
- 108773-18, SunOS 5.8: IIIM and X I/O Method patch
- 108921-16, CDE 1.4: dtwm patch
- 108940-53, Motif 1.2.7 and 2.1.1: Runtime lib. patch for Solaris 8

For more information about silent installations, refer to [Appendix B](#).

To ensure that the system meets these requirements:

1. To determine whether an operating system patch is installed, enter a command similar to the following:

```
# /usr/sbin/patchadd -p | grep patch_number(without version number)
```

For example, to determine if any version of the 111713 patch is installed, use the following command:

```
# /usr/sbin/patchadd -p | grep 111713
```

If an operating system patch is not installed, then download it from the following Web site and install it:

<http://sunsolve.sun.com>

2. If you require a CSD or a SupportPac for WebSphere MQ, then refer to the following Web site for download and installation information:

<http://www-306.ibm.com/software/integration/wmq/support>

Check Kernel Parameters

Note: The kernel parameter and shell limit values shown in the following section are recommended values only. For production database systems, Oracle recommends that you tune these values to optimize the performance of the system. Refer to your operating system documentation for more information about tuning kernel parameters.

Verify that the kernel parameters shown in the following table are set to values greater than or equal to the recommended value shown on Solaris 8 and Solaris 9 operating systems. The procedure following the table describes how to verify and set the values.

Parameter	Recommended Value
noexec_user_stack	1
semsys:seminfo_semmni	100
semsys:seminfo_semmns	1024
semsys:seminfo_semmsl	256
semsys:seminfo_semvmx	32767
shmsys:shminfo_shmmax	4294967295
shmsys:shminfo_shmmin	1
shmsys:shminfo_shmmni	100
shmsys:shminfo_shmseg	10

Note: The following parameters are obsolete in Solaris 9:

- shmsys:shminfo_shmmin
 - shmsys:shminfo_shmseg
-

On Solaris 10, verify that the kernel parameters shown in the following table are set to values greater than or equal to the recommended value shown. The table also contains the resource controls that replace the `/etc/system` file for a specific kernel parameter.

Note: In Solaris 10, you are not required to make changes to the `/etc/system` file to implement the System V TPC. Solaris 10 uses the resource control facility for its implementation.

Parameter	Replaced by Resource Control	Recommended Value
<code>noexec_user_stack</code>	NA	1
<code>semsys:seminfo_semmni</code>	<code>project.max-sem-ids</code>	100
<code>semsys:seminfo_semmsl</code>	<code>process.max-sem-nsems</code>	256
<code>shmsys:shminfo_shmmax</code>	<code>project.max-shm-memory</code>	4294967295
<code>shmsys:shminfo_shmmni</code>	<code>project.max-shm-ids</code>	100

On Solaris 8 and Solaris 9 operating systems, use the following procedure to view the current value specified for these kernel parameters, and to change them if necessary:

1. To view the current values of these parameters, enter the following commands:

```
# grep noexec_user_stack /etc/system
# /usr/sbin/sysdef | grep SEM
# /usr/sbin/sysdef | grep SHM
```

2. If you must change any of the current values, then:

- a. Create a backup copy of the `/etc/system` file, for example:

```
# cp /etc/system /etc/system.orig
```

- b. Open the `/etc/system` file in any text editor and, if necessary, add lines similar to the following (edit the lines if the file already contains them):

```
set noexec_user_stack=1
set semsys:seminfo_semmni=100
set semsys:seminfo_semmns=1024
set semsys:seminfo_semmsl=256
set semsys:seminfo_semvms=32767
set shmsys:shminfo_shmmax=4294967295
set shmsys:shminfo_shmmni=1
set shmsys:shminfo_shmmni=100
set shmsys:shminfo_shmseg=10
```

- c. Enter the following command to restart the system:

```
# /usr/sbin/reboot
```

- d. When the system restarts, log in and switch user to root.

On Solaris 10, use the following procedure to view the current value specified for resource controls, and to change them if necessary:

1. To view the current values of the resource control, enter the following commands:

```
# id -p // to verify the project id
uid=0(root) gid=0(root) projid=1 (user.root)
```

```
# prctl -n project.max-shm-memory -i project user.root
# prctl -n project.max-sem-ids -i project user.root
```

2. If you must change any of the current values, then:

a. To modify the value of max-shm-memory to 6 GB:

```
# prctl -n project.max-shm-memory -v 6gb -r -i project user.root
```

b. To modify the value of max-sem-ids to 256:

```
# prctl -n project.max-sem-ids -v 256 -r -i project user.root
```

Check the Database Requirements

In order to install Oracle Database Vault, you must be running the Enterprise Edition of Oracle Database 10g 10g Release 2 (10.2.0.5). The database should also have Oracle Enterprise Manager Console DB 10.2.0.5.0 installed. In addition, the Database Vault installer requires write access to the files, `oratab` and `oraInst.loc`.

A listener must have been configured for the existing database. Oracle Net Configuration Assistant configures the listener when you first install the database. You can also use Oracle Enterprise Manager to administer listeners.

You must have an existing password file for the database. The password file authentication parameter, `REMOTE_LOGIN_PASSWORDFILE` must have been set to `EXCLUSIVE` or `SHARED`.

You can set the `REMOTE_LOGIN_PASSWORDFILE` parameter in the `init.ora` file. Use the `orapwd` utility to create and manage password files.

See Also: *Oracle Database Administrator's Guide* for more information on creating and maintaining a password file

The following topics discuss applying the 10.2.0.5 patch set and installing the required components:

- [Install Oracle Enterprise Manager Console DB](#)
- [Apply Oracle Database Release 10.2.0.5 Patch Set](#)

Install Oracle Enterprise Manager Console DB

Before installing Oracle Database Vault, you should ensure that Oracle Enterprise Manager Console DB 10.2.0.5.0 is installed. Oracle Enterprise Manager Console DB is installed using the Oracle Universal Installer (OUI). The following steps summarize installing Oracle Enterprise Manager Console DB:

1. Run Oracle Universal Installer (OUI) and perform a custom installation to install Oracle Enterprise Manager Console DB 10.2.0.5.0. Add Oracle Enterprise Manager Console DB from the list of available product components.
2. Apply the Oracle Database release 10.2.0.5 patch set.

Note: You can configure the database to use Enterprise Manager Database Control by using Database Configuration Assistant (DBCA). However, configuring Enterprise Manager Database Control is not a prerequisite for installing Oracle Database Vault.

Apply Oracle Database Release 10.2.0.5 Patch Set

To install Oracle Database Vault, you need to upgrade the database to Oracle Database release 10.2.0.5. Oracle strongly recommends that you back up your database before performing any upgrade or installation.

See Also: *Oracle Database Backup and Recovery User's Guide* for information on database backups

This section covers the following topics:

Patch Set Overview

You can apply the Oracle Database release 10.2.0.5 patch set to the following Oracle Database 10g release 2 installations:

- Oracle Database
- Oracle Real Application Clusters
- Oracle Database Client
- Oracle Database Companion CD
- Oracle Clusterware
- Oracle Database Vault

Oracle Universal Installer Version Requirements

This patch set includes Oracle Universal Installer release 10.2.0.5, which is also installed when you install this patch set. This is to ensure that your Oracle home can be patched in the future. You should not use the Installer from the earlier maintenance release media or Oracle home.

This is not a complete software distribution. You must install it in an existing Oracle Database 10g release 2 installation.

Patch Set Documentation

There are two documents related to this release of the Oracle Database patch set:

- *Oracle Database Patch Set Notes, 10g Release 2 (10.2.0.5) Patch Set for Solaris Operating System (SPARC 64-Bit)*
- *Oracle Database List of Bugs Fixed, 10g Release 2 (10.2.0.5) Patch Set*

Both of these documents are included with the patch set. In addition, they are available on the My Oracle Support (formerly OracleMetalink) Web site:

<https://support.oracle.com>

Prepare a Backup Strategy

Oracle strongly recommends that you back up your database before performing any upgrade or installation. The ultimate success of your upgrade depends heavily on the design and execution of an appropriate backup strategy. To develop a backup strategy, consider the following questions:

- How long can the production database remain inoperable before business consequences become intolerable?
- What backup strategy should be used to meet your availability requirements?

- Are backups archived in a safe, offsite location?
- How quickly can backups be restored (including backups in offsite storage)?
- Have recovery procedures been tested successfully?

Your backup strategy should answer all of these questions and include procedures for successfully backing up and recovering your database.

See Also: *Oracle Database Backup and Recovery User's Guide* for information on database backups

Disable Custom Profiles (If Any)

If you have created custom profiles and password complexity checks in your existing database, then you need to disable these before performing the installation. You can reenable these after the installation is complete. Use the following steps to achieve this:

1. Extract the profile names and associated settings for each profile that is being used. You can use a script to accomplish this.

[Example 2–1](#) shows a sample script that extracts the profile names and settings to create an output script called, `myprofiles.sql`. After the installation is complete, you can run `myprofiles.sql` to restore the profile settings.

Example 2–1 Extracting Profiles

```
set serverout on size 100000
spool myprofiles.sql
.
declare
l_last varchar2(30) := 'X';
l_count number := 0;
begin
  for c in (
    select profile, resource_name , limit
    from dba_profiles
    order by profile, resource_name
  ) loop
    if l_last <> c.profile then
      l_last := c.profile;
      if l_count > 0 then
        dbms_output.put_line(';');
      end if;
      l_count := l_count + 1;
      dbms_output.put_line('create profile ' || c.profile || ' limit ');
    else
      dbms_output.put_line('      ' || c.resource_name || ' ' || c.limit);
    end if;
  end loop;
  dbms_output.put_line(';');
end;
/
.
spool off
```

2. Disable the custom profiles and password complexity settings. For example:

```
SQL> ALTER PROFILE SomeCustomProfile LIMIT
PASSWORD_REUSE_MAX UNLIMITED -- The number of times a password can be reused
PASSWORD_REUSE_TIME UNLIMITED -- The number of days between reuses of a
password
```

```
PASSWORD_VERIFY_FUNCTION NULL
/
```

3. After the Oracle Database Vault installation is complete, reenable the profiles by running the script created in Step 1.

```
SQL>@myprofiles.sql
```

Verify That Oracle Clusterware Is Running (Oracle RAC Only)

Oracle Clusterware should be running for the Database Vault installer to find the existing Oracle Real Application Clusters (Oracle RAC) instances. If you have stopped Oracle Clusterware, then you should restart it before running Oracle Universal Installer. Use the following command to start Oracle Clusterware:

```
$CRS_HOME/bin/crsctl start crs
```

Note:

- You must run the `crsctl` command as the `root` user. You need to run this command on all cluster nodes.
 - The `crsctl start crs` command also starts the database. You will need to shut down the database before running Oracle Universal Installer.
-
-

Stop Existing Oracle Processes

Stop all processes running in the Oracle home, except the database listener. You must complete this task to enable Oracle Universal Installer to relink certain executables and libraries. For Oracle RAC databases, you need to stop the processes on all nodes.

Stop the processes in the following order:

1. [Stop the Enterprise Manager Database Control Process](#)
2. [Stop the iSQL*Plus Process](#)
3. [Shut Down All Database Instances](#)

Stop the Enterprise Manager Database Control Process

Stop the Enterprise Manager Database Control process, if it is running. Use the following command:

```
$ORACLE_HOME/bin/emctl stop dbconsole
```

Stop the iSQL*Plus Process

Stop the iSQL*Plus process, using the following command:

```
$ORACLE_HOME/bin/isqlplusctl stop
```

Shut Down All Database Instances

Shut down all database instances running from the Oracle home directory into which Oracle Database Vault is to be installed.

```
sqlplus SYS "AS SYSDBA"
Enter password:
SQL> shutdown immediate
```

Configure the Oracle User's Environment

Run Oracle Universal Installer (OUI) using the account that owns the Oracle software. This is usually the `oracle` account.

However, before you start Oracle Universal Installer you must configure the environment of the `oracle` user. To configure the environment, you must:

- Set the default file mode creation mask (`umask`) to 022 in the shell startup file.
- Set the `DISPLAY` environment variable.

Note: Ensure that the `PATH` variable contains `$ORACLE_HOME/bin` before `/usr/X11R6/bin`.

To set the `oracle` user's environment:

1. Start a new terminal session, for example, an X terminal (`xterm`).
2. Enter the following command to ensure that X Window applications can display on this system:

```
$ xhost fully_qualified_remote_host_name
```

For example:

```
$ xhost somehost.us.acme.com
```

3. If you are not already logged in to the system where you want to install the software, then log in to that system as the `oracle` user.
4. If you are not logged in as the `oracle` user, then switch user to `oracle`:

```
$ su - oracle
```

5. To determine the default shell for the `oracle` user, enter the following command:

```
$ echo $SHELL
```

6. Open the `oracle` user's shell startup file in any text editor:

- Bourne shell (`sh`), Bash shell (`bash`), or Korn shell (`ksh`):

```
$ vi .bash_profile
```

- C shell (`csh` or `tcsh`):

```
% vi .login
```

7. Enter or edit the following line, specifying a value of 022 for the default file mode creation mask:

```
umask 022
```

8. If the `ORACLE_SID`, `ORACLE_HOME`, or `ORACLE_BASE` environment variable is set in the file, then remove the corresponding lines from the file.

9. Save the file, and exit from the editor.

10. To run the shell startup script, enter one of the following commands:

- Bourne, Bash, or Korn shell:

```
$ . ./profile
```

- C shell:

```
% source ~/.login
```

11. If you are not installing the software on the local system, then enter a command similar to the following to direct X applications to display on the local system:

- Bourne, Bash, or Korn shell:

```
$ DISPLAY=local_host:0.0 ; export DISPLAY
```

- C shell:

```
% setenv DISPLAY local_host:0.0
```

In this example, *local_host* is the host name or IP address of the system that you want to use to display Oracle Universal Installer (your workstation or PC).

12. If you determined that the /tmp directory has less than 400 MB of free disk space, then identify a file system with at least 400 MB of free space and set the TEMP and TMPDIR environment variables to specify a temporary directory on this file system:

- a. Use the `df -k` command to identify a suitable file system with sufficient free space.

- b. If necessary, enter commands similar to the following to create a temporary directory on the file system that you identified, and set the appropriate permissions on the directory:

```
$ su - root
# mkdir /mount_point/tmp
# chmod a+wr /mount_point/tmp
# exit
```

- c. Enter commands similar to the following to set the TEMP and TMPDIR environment variables:

- * Bourne, Bash, or Korn shell:

```
$ TEMP=/mount_point/tmp
$ TMPDIR=/mount_point/tmp
$ export TEMP TMPDIR
```

- * C shell:

```
% setenv TEMP /mount_point/tmp
% setenv TMPDIR /mount_point/tmp
```

13. Enter commands similar to the following to set the ORACLE_BASE and ORACLE_SID environment variables:

- Bourne, Bash, or Korn shell:

```
$ ORACLE_BASE=/u01/app/oracle
$ ORACLE_SID=sales
$ export ORACLE_BASE ORACLE_SID
```

- C shell:

```
% setenv ORACLE_BASE /u01/app/oracle
% setenv ORACLE_SID sales
```

In these examples, `/u01/app/oracle` is the Oracle base directory that you created or identified earlier and `sales` is the name that you want to call the database (typically no more than five characters).

14. Enter the following commands to ensure that the `ORACLE_HOME` and `TNS_ADMIN` environment variables are not set:

- Bourne, Bash, or Korn shell:

```
$ unset ORACLE_HOME
$ unset TNS_ADMIN
```

- C shell:

```
% unsetenv ORACLE_HOME
% unsetenv TNS_ADMIN
```

15. To verify that the environment has been set correctly, enter the following commands:

```
$ umask
$ env | more
```

Verify that the `umask` command displays a value of 22, 022, or 0022 and the environment variables that you set in this section have the correct values.

Run Oracle Universal Installer to Install Oracle Database Vault

Run Oracle Universal Installer (OUI) to install Oracle Database Vault into an existing Oracle Database 10g Release 2 (10.2.0.5) database. You should run the installer as the software owner account that owns the current `ORACLE_HOME` environment. This is normally the `oracle` account.

Log in as the `oracle` user. Alternatively, switch user to `oracle` using the `su` command. Change your current directory to the directory containing the installation files. Start Oracle Universal Installer.

```
./runInstaller
```

The following steps discuss the options you need to select:

1. In the Specify Installation Details screen, you need to specify the path to the Oracle home that contains the existing Oracle Database. The **Destination Path** box lists the Oracle home paths of all Oracle Database 10g Release 2 (10.2.0.5) Enterprise Edition databases registered with the system.

Select the Oracle home corresponding to the database into which you want to install Oracle Database Vault.

Note:

- If an Oracle home does not have an Enterprise Edition of Oracle Database release 10.2.0.5 installed, then it is not displayed. You must ensure that the Oracle home has an Enterprise Edition of Oracle Database release 10.2.0.5 installed.
 - If an Oracle home does not have Oracle Enterprise Manager Console DB 10.2.0.5.0 installed, then it is not displayed. You must ensure that the Oracle home has Oracle Enterprise Manager Console DB 10.2.0.5.0 installed.
 - If an Oracle home contains an Automatic Storage Management (ASM) instance, then it is not displayed. You cannot install Oracle Database Vault into an Oracle home that also contains an ASM instance.
 - If an Oracle home already contains Oracle Database Vault, then it is not displayed. You cannot install Oracle Database Vault into an Oracle home more than once.
-

2. Enter a user name for the Database Vault Owner account in the **Database Vault Owner** field. The user name can be a minimum of 2 and maximum of 30 characters long.
3. Enter a password for the Database Vault Owner account in the **Database Vault Owner Password** field. The password can be a minimum of 8 and a maximum of 30 characters. The password must include at least one alphabet, one digit, and one nonalphanumeric character (symbol). It cannot be the same as the account names for either the Database Vault owner or the Database Vault account manager. It cannot contain any consecutive repeating characters.
4. Reenter the password in the **Confirm Password** field.
5. Select **Create a Separate Account Manager** if you want to create a separate Account Manager to manage Oracle Database Vault accounts.
6. In the **Database Vault Account Manager** field, enter a user name for the Database Vault Account Manager if you have chosen to select the **Create a Separate Account Manager** check box. The user name can be a minimum of 2 and a maximum of 30 characters.
7. Enter a password for the Database Vault Account Manager account in the **Account Manager Password** field. The password can be a minimum of 8 and a maximum of 30 characters. The password must include at least one alphabet, one digit, and one nonalphanumeric character (symbol). It cannot be the same as the account names for either the Database Vault owner or the Database Vault account manager. It cannot contain any consecutive repeating characters.
8. Reenter the password in the **Confirm Password** field. Click **Next**.
9. The Select Existing Database screen is displayed. A list of all databases running from the selected Oracle home is displayed. Select the database into which you wish to install Oracle Database Vault.

Note:

- Oracle recommends that you install Oracle Database Vault into an Oracle home containing only a single database.

If there are multiple databases in an Oracle home, you must enable Database Vault for all the databases. You cannot have Database Vault enabled databases coexist with non-Database Vault enabled databases in the same Oracle home. In order to enable Database Vault for additional databases in the same Oracle home, refer to [Appendix C, "Running DVCA After Creating a Database Vault Database"](#)

- If a database is not listed, then check to make sure that you have followed the instructions under "[Check the Database Requirements](#)" on page 2-8.
-

10. Enter the existing SYS user password for the selected database in the **Existing Database SYS Password** field.

11. Reenter the SYS password in the **Confirm Password** field. Click **Next**.

Note: At this point, the database requirements are validated.

12. You are prompted to shut down all Oracle processes running from the Oracle home before proceeding. Shut down the Oracle processes, if you have not already done so.

See Also: "[Stop Existing Oracle Processes](#)" on page 2-11 for more information on stopping existing Oracle processes

13. Product-specific prerequisite checks are performed. Confirm that all tests have passed. Click **Next** to continue.

14. The Summary screen is displayed with the installation details. Verify the details and click **Install**.

15. The Installation screen is displayed. After the installation completes, the Database Vault Configuration Assistant (DVCA) is run automatically. DVCA helps configure the Database Vault installation.

Postinstallation Tasks

This section lists the tasks to perform after you have completed an upgrade of your database. The following topics are discussed:

- [Back Up the Database](#)
- [Update Environment Variables After the Upgrade \(UNIX Systems Only\)](#)
- [Change Passwords for Oracle-Supplied Accounts](#)
- [Disable Remote SYSDBA Connections \(Optional\)](#)
- [Start the Database on Other Nodes \(Oracle RAC Only\)](#)
- [Configure Oracle Database Vault on Oracle RAC Nodes \(Oracle RAC Only\)](#)
- [Set the Timeout Value for DVA \(Optional\)](#)

- [Manually Deploy Oracle Database Vault Administrator \(Special Cases\)](#)

Back Up the Database

Make sure you perform a full backup of the production database. See *Oracle Database Backup and Recovery User's Guide* for details on backing up a database.

Update Environment Variables After the Upgrade (UNIX Systems Only)

Make sure that the following environment variables point to the correct Oracle Database Vault directories:

- ORACLE_HOME
- PATH
- ORA_NLS10

Note: The ORA_NLS10 environment variable replaces the ORA_NLS33 environment variable, so you may need to unset ORA_NLS33 and set ORA_NLS10.

- LD_LIBRARY_PATH

Change Passwords for Oracle-Supplied Accounts

Oracle strongly recommends that you change the password for each account after installation. This enables you to effectively implement the strong security provided by Oracle Database Vault.

Note: If you are creating a database using Database Configuration Assistant, you can unlock accounts after the database is created by clicking **Password Management** before you exit from Database Configuration Assistant.

Using SQL*Plus to Unlock Accounts and Reset Passwords

To unlock and reset user account passwords using SQL*Plus:

1. Start SQL*Plus and log in using the Database Vault Account Manager account. If you did not create the Database Vault Account Manager account during installation, then you will need to log in using the Database Vault Owner account.
2. Enter a command similar to the following, where *account* is the user account that you want to unlock and *password* is the new password:

```
SQL> ALTER USER account [ IDENTIFIED BY password ] ACCOUNT UNLOCK;
```

In this example:

- The ACCOUNT UNLOCK clause unlocks the account.
- The IDENTIFIED BY *password* clause resets the password.

Note: If you unlock an account but do not reset the password, then the password remains expired. The first time someone connects as that user, they must change the user's password.

To permit unauthenticated access to your data through HTTP, unlock the ANONYMOUS user account.

See Also: *Oracle Database Administrator's Guide* for more information about:

- Unlocking and changing passwords after installation
- Oracle security procedures
- Best security practices

Disable Remote SYSDBA Connections (Optional)

Oracle Database Vault allows you to disable remote logins with SYSDBA privileges. This enables enhanced security for your database.

To disable remote SYSDBA connections, re-create the password file with the nosysdba flag set to y (Yes). A user can still log in AS SYSDBA locally using Operating System (OS) authentication. However, remote connections AS SYSDBA will fail.

Use the following syntax to re-create the password file:

```
orapwd file=filename password=password [entries=users] force=y nosysdba=y
```

Where:

- **file:** Name of password file (mandatory)
- **password:** Password for SYS (mandatory). Enter at least six alphanumeric characters.
- **entries:** Maximum number of distinct DBA users
- **force:** Whether to overwrite the existing file
- **nosysdba:** Whether to enable or disable the SYS logon

The default is no, so if you omit this flag, the password file will be created enabling SYSDBA access for Oracle Database Vault instances.

For example:

```
orapwd file=$ORACLE_HOME/dbs/orapworcl password=5hjk99 force=y nosysdba=y
```

Note: Do not insert spaces around the equal (=) character.

See Also: *Oracle Database Administrator's Guide* for more information on using the orapwd utility.

When you re-create the password file, any accounts other than SYS that were granted the SYSDBA or SYSOPER privileges will have those privileges removed. You will need to regrant the privileges for these accounts after you have re-created the password file.

You can reenable the ability to connect with the `SYSDBA` privilege by re-creating the password file with the `nosysdba` flag set to `n` (No). You might need to reenable the ability to connect with `SYSDBA` privileges, if certain products or utilities require its use.

Enabling or Disabling Connecting with SYSDBA on Oracle Real Application Clusters Systems

Under a cluster file system and raw devices, the password file under `$ORACLE_HOME` is in a symbolic link that points to the shared storage location in the default configuration. In this case, the `orapwd` command you issue affects all nodes.

Enabling or Disabling Connecting with SYSDBA on Automatic Storage Management Systems

For Automatic Storage Management systems, you need to update each node to enable or disable the `SYSDBA` connection privilege by using the `orapwd` utility.

Start the Database on Other Nodes (Oracle RAC Only)

You need to start the database on all Oracle RAC nodes other than the one on which the installation is performed. Use the following command to start the database:

Note: You need `SYSDBA` privileges to run these commands.

```
srvctl start instance -d sid -i instance_name
```

Note: You must use the Server Control (`srvctl`) utility to start and stop Oracle RAC instances. Do not use SQL*Plus to start and stop Oracle RAC instances.

Configure Oracle Database Vault on Oracle RAC Nodes (Oracle RAC Only)

You need to run this command on all Oracle RAC nodes other than the node on which the Database Vault installation is performed. This step is required to enable the enhanced security features provided by Oracle Database Vault.

Note: The `dvca -action optionrac` option has been deprecated and can no longer be used to configure Oracle RAC nodes.

1. Log in to SQL*Plus as user `SYS` with the `SYSDBA` privilege.

```
sqlplus sys as sysdba
Enter password: password
```

2. Run the following `ALTER SYSTEM` statements:

```
ALTER SYSTEM SET AUDIT_SYS_OPERATIONS=TRUE SCOPE=SPFILE;
ALTER SYSTEM SET OS_ROLES=FALSE SCOPE=SPFILE;
ALTER SYSTEM SET RECYCLEBIN='OFF' SCOPE=SPFILE;
ALTER SYSTEM SET REMOTE_LOGIN_PASSWORDFILE='EXCLUSIVE' SCOPE=SPFILE;
ALTER SYSTEM SET SQL92_SECURITY=TRUE SCOPE=SPFILE;
ALTER SYSTEM SET OS_AUTHENT_PREFIX=' ' SCOPE=SPFILE;
```

3. Restart Oracle Database

```
$ORACLE_HOME/bin/srvctl stop database -d db_name  
$ORACLE_HOME/bin/srvctl start database -d db_name
```

Set the Timeout Value for DVA (Optional)

Oracle Database Vault Administrator (DVA) is a browser-based graphical user interface console that you can use to manage Oracle Database Vault.

You can modify the length of time that DVA stays connected while inactive. By default, the connection duration is 35 minutes. Your session automatically gets expired after 35 minutes of inactivity.

To set the session time for Oracle Database Vault Administrator:

1. Back up the `web.xml` file, which by default is in the `$ORACLE_HOME/dv/jlib/dva_webapp/dva_webapp/WEB-INF` directory.
2. In a text editor, open the `web.xml` file .
3. Search for the following setting:

```
<session-config>  
  <session-timeout>35</session-timeout>  
</session-config>
```
4. Change the `<session-timeout>` setting to the amount of time in minutes that you prefer.
5. Save and close the `web.xml` file.
6. Stop and restart the DVA application.

You can use the following command to restart DVA:

```
emctl stop dbconsole  
emctl start dbconsole
```

Manually Deploy Oracle Database Vault Administrator (Special Cases)

If you have created an Oracle database manually, and have configured Oracle Enterprise Manager Database Control by using Enterprise Manager Configuration Assistant, you must manually deploy Oracle Database Vault Administrator. This procedure deploys Database Vault Administrator in the same OC4J container as the current Enterprise Manager, rather than creating a new application.

This section contains:

- [Deploying Database Vault Administrator to a Standalone OC4J Container](#)
- [Deploying Database Vault Administrator to the Database Console OC4J Container](#)

Deploying Database Vault Administrator to a Standalone OC4J Container

You can manually deploy Database Vault Administrator to the Oracle Application Server Containers for J2EE (OC4J) home, which by default is in the `$ORACLE_HOME/oc4j/j2ee/home` directory.

To manually deploy Database Vault Administrator:

1. Edit the file `$ORACLE_HOME/oc4j/j2ee/home/config/server.xml`. Enter the following line just before the last line that reads, `</application-server>`:

```
<application name="dva" path="$ORACLE_HOME/dv/jlib/dva_webapp.ear"  
auto-start="true" />
```

For example:

```
<application name="dva"
path="/u00/app/oracle/oracle/product/dv12/dv/jlib/dva_webapp.ear"
auto-start="true" />
```

2. Edit the file

`$ORACLE_HOME/oc4j/j2ee/home/config/http-web-site.xml`. Enter the following line just above the last line that reads, `</web-site>`:

```
<web-app application="dva" name="dva_webapp" root="/dva" />
```

3. Edit the file

`$ORACLE_HOME/oc4j/j2ee/home/config/global-web-application.xml`

. Search for

```
<servlet-class>oracle.jsp.runtimev2.JspServlet</servlet-class>
>. Uncomment the following lines after this:
```

```
<init-param>
  <param-name>main_mode</param-name>
  <param-value>justrun</param-value>
</init-param>
```

4. Create the following directory:

```
mkdir -p $ORACLE_HOME/dv/jlib/sysman/config
```

5. Create the database connection configuration file, `emoms.properties`, in the configuration directory that you just created. Add the following lines to the file:

```
oracle.sysman.emSDK.svlt.ConsoleMode=standalone
oracle.sysman.eml.mntr.emdRepRAC=FALSE
oracle.sysman.eml.mntr.emdRepDBName=oracle_sid
oracle.system.eml.mntr.emdRepConnectDescriptor=TNS_connection_string
```

Follow these instructions:

- For an Oracle RAC environment, set `oracle.sysman.eml.mntr.emdRepRAC` to TRUE.
- For `oracle.sysman.eml.mntr.emdRepConnectDescriptor`, you can use an alias from `$ORACLE_HOME/network/admin/tnsnames.ora`. Alternatively, you can use the following syntax:

```
oracle.sysman.eml.mntr.emdRepConnectDescriptor=
(DESCRIPTION=
  (ADDRESS_LIST=(ADDRESS=(PROTOCOL=TCP) (HOST=HOSTNAME) (PORT=PORT)))
  (CONNECT_DATA=
    (SERVICE_NAME=ORACLE_SID))
```

6. Ensure that the correct environment variables are set.

For example:

```
ORACLE_SID=orcl
export ORACLE_SID
ORACLE_HOME=/u00/app/oracle/product/11.1/dv
export ORACLE_HOME
LD_LIBRARY_PATH=$ORACLE_HOME/bin:$ORACLE_HOME/lib32:$ORACLE_HOME/lib:$ORACLE_HO
ME/jdbc/lib
export LD_LIBRARY_PATH
PATH=$ORACLE_HOME/bin:$ORACLE_HOME/jdk/bin:$PATH
```

```
export PATH
```

Ensure that you set the `LD_LIBRARY_PATH` variable to use the OCI-based JDBC libraries.

7. Start OC4J using the following syntax:

```
$ORACLE_HOME/jdk/bin/java -Djava.awt.headless=true  
-DEMDROOT=$ORACLE_HOME/dv/jlib -jar $ORACLE_HOME/oc4j/j2ee/home/oc4j.jar  
-userThreads -config $ORACLE_HOME/oc4j/j2ee/home/config/server.xml
```

After you complete these steps, you can start Database Vault Administrator. The HTTP port defaults to 8888 for this environment. Use the following syntax for the URL:

```
http://hostname:8888/dva
```

Deploying Database Vault Administrator to the Database Console OC4J Container

To manually deploy Database Vault Administrator to the Database Console OC4J container:

1. Stop Oracle Database Console.

- **UNIX:** Go to the `$ORACLE_HOME/bin` directory and run the following command:

```
./emctl stop dbconsole
```
- **Microsoft Windows:** In the Administrative Services, select the Services utility, and then right-click the **OracleDBConsolesid** service. Select **Stop** from the menu.

2. Create a backup copy and then open the

```
$ORACLE_HOME/oc4j/j2ee/OC4J_DBConsole_service_name/config/server.xml
```

 file.

3. Add the following line before the `</application-server>` element:

```
<application name="dva" path="$ORACLE_HOME/dv/jlib/dva_webapp.ear"  
parent="default" start="true" />
```

On Windows systems, replace `$ORACLE_HOME` with the absolute path to your Oracle Database home.

4. Create a backup copy and then open the

```
$ORACLE_HOME/oc4j/j2ee/OC4J_DBConsole_service_name/config/http-web-site.xml
```

 file.

5. Add the following line before the `</web-site>` element:

```
<web-app application="dva" name="dva_webapp" load-on-startup="true" root="/dva"  
shared="true"/>
```

6. Restart Oracle Database Console.

- **UNIX:** Go to the `$ORACLE_HOME/bin` directory and run the following command:

```
./emctl start dbconsole
```
- **Windows:** In the Administrative Services, select the Services utility, and then right-click the **OracleDBConsolesid** service. Select **Start** from the menu.

After you complete these steps, you can start Oracle Database Vault Administrator by using the following URL:

`https://hostname:port/dva`

For example:

`https://myserver:1158/dva`

If you are unsure of the port number, open the `ORACLE_HOME/host_sid/sysman/config/emd.properties` file and search for `REPOSITORY_URL`. In most cases, the host name and port number are the same as Oracle Enterprise Manager Database Control.

Removing Oracle Database Vault

The following procedures uninstall Oracle Database Vault from an Oracle Database installation. They apply to both single-instance and Oracle RAC installations.

- [Step 1: Deconfigure Oracle Database Vault](#)
- [Step 2: Deinstall Oracle Database Vault](#)

Step 1: Deconfigure Oracle Database Vault

1. Disable Oracle Database Vault, as described under "Step 1: Disable Oracle Database Vault" in *Oracle Database Vault Administrator's Guide*.
2. In SQL*Plus, connect as user SYS with the SYSDBA privilege.

```
CONNECT SYS/AS SYSDBA
Enter password: password
```

3. Disable the recycle bin.

To check if the recycle bin is enabled, enter the following command:

```
SHOW PARAMETER RECYCLEBIN
```

If it is enabled, then run the following SQL statement:

```
ALTER SYSTEM SET RECYCLEBIN = OFF;
```

Disabling the recycle bin does not purge or otherwise affect objects that are already in the recycle bin.

4. Run the following SQL script:
5. Manually drop the DV_OWNER and DV_ACCTMGR user accounts.

```
@$ORACLE_HOME/rdbms/admin/dvremov.sql
```

For example:

```
DROP USER dbv_owner CASCADE;
DROP USER dbv_acctmgr CASCADE;
```

6. Restart the database.

For example:

```
SHUTDOWN IMMEDIATE
STARTUP
```

Step 2: Deinstall Oracle Database Vault

1. Start OUI by invoking `runInstaller` from the `$ORACLE_HOME/oui/bin` directory.
2. In the Welcome window, select **Deinstall Products**.
3. Navigate to the correct directory and then select **Database Vault 10.2.0.5** from the list.
4. In the confirmation window, select **Yes**.
5. Exit OUI.

Afterward, you can double-check that Oracle Database Vault is truly deinstalled by logging in to SQL*Plus and entering the following statement:

```
SELECT * FROM V$OPTION WHERE PARAMETER = 'Oracle Database Vault';
```

If Oracle Database Vault is deinstalled, the following output appears:

PARAMETER	VALUE
Oracle Database Vault	FALSE

Part II

Appendixes

Part II includes the appendixes. The contents of this part are:

- [Appendix A, "How to Stop Processes in an Existing Oracle Real Application Clusters Database"](#)
- [Appendix B, "Using Response Files"](#)
- [Appendix C, "Running DVCA After Creating a Database Vault Database"](#)
- [Appendix D, "Upgrading from a Previous Version of Database Vault"](#)
- [Appendix E, "Database Listener Security Recommendations"](#)
- [Appendix F, "Initialization Parameters"](#)
- [Appendix G, "Enabling Oracle Database Vault Administrator Accessibility"](#)

How to Stop Processes in an Existing Oracle Real Application Clusters Database

This appendix describes how to stop all processes in an Oracle Real Application Clusters (Oracle RAC) database, in preparation for installing Database Vault.

Note: Before you make any changes to the Oracle software, Oracle recommends that you create a backup of the Oracle Database installation.

To stop all processes in an Oracle Real Application Clusters (Oracle RAC) database, use the following steps:

Note: You must perform these steps in the order listed.

1. Make sure that the environment variables, ORACLE_HOME, ORACLE_SID, and PATH are correctly set.
2. Shut down any processes in the Oracle home on each node that can access a database. For example, you need to shut down Oracle Enterprise Manager Database Control.

```
$ORACLE_HOME/bin/emctl stop dbconsole
```

Note:

- You must run the preceding command on all nodes.
 - Before you shut down any processes that are monitored by Enterprise Manager Grid Control, set a blackout in Grid Control for the processes that you intend to shut down. This is necessary so that the availability records for these processes indicate that the shutdown was planned downtime, rather than an unplanned system outage.
-

3. Shut down all Oracle RAC instances on all nodes. To shut down all Oracle RAC instances for a database, enter the following command, where *db_name* is the name of the database:

```
$ oracle_home/bin/srvctl stop database -d db_name
```

Using Response Files

This appendix describes how to install Oracle Database Vault using a response file. It includes the following topics:

- [How Response Files Work](#)
- [Installing Database Vault Using a Response File](#)
- [Troubleshooting Silent Mode Installation](#)

How Response Files Work

You can automate the installation and configuration of Oracle software by specifying a response file when you start Oracle Universal Installer. Oracle Universal Installer uses the values contained in the response file to provide answers to some or all of Oracle Universal Installer prompts.

Typically, Oracle Universal Installer runs in interactive mode, which means that it prompts you to provide information in graphical user interface (GUI) screens. When you use response files to provide this information, you run Oracle Universal Installer at a command prompt using the silent mode.

During a silent mode installation, Oracle Universal Installer does not display any screens. Instead, it displays progress information in the terminal that you used to start it.

You define the settings for a silent mode installation by entering values for the variables listed in the response file. For instance, to specify the Oracle home, you would supply the appropriate value for the `ORACLE_HOME` variable, as in the following example:

```
ORACLE_HOME = "/home/Oracle/OraDBHome1"
```

Another way of specifying the response file's variable settings is to pass them as command line arguments when you run Oracle Universal Installer. For example:

```
$ /directory_path/runInstaller -silent "ORACLE_HOME=/home/Oracle/OraDBHome1" ...
```

In this command, *directory_path* is the path to the database directory on the DVD or the path to the `Disk1` directory on the hard drive.

This method is particularly useful if you do not want to embed sensitive information, such as passwords, in the response file. For example:

```
$ /directory_path/runInstaller -silent "s_ownerPasswd=binks342" ...
```

Ensure that you enclose the variable and its setting in double quotation marks (" ").

See Also: *Oracle Universal Installer and OPatch User's Guide* for more information about response file formats

General Procedure for Using Response Files

The following are the general steps to install and configure Oracle products using Oracle Universal Installer in silent mode:

Note: You must complete all required preinstallation tasks on a system before running Oracle Universal Installer in silent mode.

1. Verify that the `oraInst.loc` file exists in the `/var/opt/oracle` directory.
2. Prepare a response file.
3. Run Oracle Universal Installer in silent mode.

Installing Database Vault Using a Response File

Use the following steps to install Database Vault using a response file:

Note: The `oraInst.loc` file should already be present in the `/var/opt/oracle` directory, by default. This is because Oracle Database Vault is installed into an existing Oracle Database installation.

1. [Prepare the Response File](#)
2. [Run Oracle Universal Installer Using the Response File](#)

Prepare the Response File

Oracle Database Vault comes with a response file template (`dv.rsp`) that you can edit to customize your installation. You can use this response file for silent mode installations.

The `dv.rsp` file is located in the `response` directory on the installation media. Use the following steps to copy and modify the response file:

1. Copy the response file from the `response` directory to a directory on your system.

```
$ cp /directory_path/response/dv.rsp local_directory
```

In this example, `directory_path` is the path to the database directory on the installation media. `local_directory` is the path to a directory on your disk.

2. Open the response file in a text editor:

```
$ vi local_directory/dv.rsp
```

The response file contains variables that store information required by Oracle Universal Installer. You need to set these variable values in the file. For example, you need to specify values for the Oracle home location, Database Vault owner name, and other such information required by Oracle Universal Installer.

The response file contains two parts. You should edit the variables only in the first part. The second part of the file contains preset variables, which must not be edited. This instruction is also provided in the response file.

Some of the variables are mandatory while others are optional. The mandatory variables must be supplied for a successful installation. Each variable is explained within the response file. Examples are also provided within the response file.

The following excerpt from the response file shows instructions related to setting the Oracle home variable:

```
#-----
--
#Name      : ORACLE_HOME
#Datatype  : String
#Description: Complete path of the existing 10.2.0.5.0 database Oracle
#           Home into which Oracle Database Vault will be installed.
#
#Requirement: 1) Must have Oracle Database Enterprise Edition release
#              10.2.0.5.0 installed.
#              2) Must have Oracle Enterprise Manager Console DB version
#              10.2.0.5.0 installed.
#              3) Cannot contain an Automatic Storage Management(ASM) instance.
#              4) Cannot contain Oracle Database Vault.
#
#Example: ORACLE_HOME = "C:\OHOM1"
#-----
--
ORACLE_HOME=<Value Required>
```

Lines starting with a pound sign (#) are comment entries. If you wish to omit an optional variable, you can comment it by adding a pound sign (#) at the beginning of the line. You cannot comment lines containing mandatory variables, like ORACLE_HOME.

Remember that you can specify sensitive information, such as passwords, at the command line rather than within the response file. ["How Response Files Work"](#) on page B-1 explains this method.

See Also: *Oracle Universal Installer and OPatch User's Guide* for detailed information on creating response files.

3. Follow the instructions in the file to edit it. Save and close the file.

Note: Oracle Universal Installer fails if you do not correctly configure the response file. Refer to the ["Troubleshooting Silent Mode Installation"](#) section on page B-4 for more information about troubleshooting a failed silent mode installation.

4. Change the permissions on the file to 700:

```
$ chmod 700 /local_dir/response_file.rsp
```

Caution: A fully specified response file for an Oracle Database Vault installation contains the passwords for database administrative accounts. Ensure that only the Oracle software owner user can view or modify response files or consider deleting them after the installation succeeds.

Run Oracle Universal Installer Using the Response File

Now, you are ready to run Oracle Universal Installer at the command line, specifying the response file you created, to perform the installation. The Oracle Universal Installer executable, `runInstaller`, provides several options. For help information on the full set of these options, run `runInstaller` with the `-help` option. For example:

```
$ directory_path/runInstaller -help
```

To run Oracle Universal using a response file:

1. Complete the preinstallation tasks listed in [Chapter 2, "Installing Oracle Database Vault"](#).

See Also: Frequently Asked Questions in the *Oracle Database Vault Release Notes for Solaris Operating System (SPARC 64-Bit)* for a checklist of the preinstallation requirements

2. Log in as the Oracle software owner user (typically `oracle`).
3. To start Oracle Universal Installer in silent mode, enter a command similar to the following:

Note: Do not specify a relative path to the response file. If you specify a relative path, Oracle Universal Installer fails.

```
$ /directory_path/runInstaller -silent -responseFile responsefilename
```

In this example:

- `directory_path` is the path to the database directory on the DVD or the path to the `Disk1` directory on the hard disk.
- `-silent` indicates that you want to run Oracle Universal Installer in silent mode.
- `responsefilename` is the full path and file name of the installation response file that you configured.

Note: For more information about other options for the `runInstaller` command, enter the following command:

```
$ /directory_path/runInstaller -help
```

Troubleshooting Silent Mode Installation

To determine whether a silent mode installation succeeds or fails, refer to the following log file:

`/oraInventory_location/logs/silentInstalldate_time.log`

The `oraInventory_location` can be found in the `/etc/oraInst.loc` file. The `inventory_loc` parameter in the `oraInst.loc` file specifies the location of the `oraInventory` directory.

A silent installation fails in the following conditions:

- You do not specify a response file
- You specify an incorrect or incomplete response file
- Oracle Universal Installer encounters an error, such as insufficient disk space
- The Database Vault installation prerequisites have not been met

Oracle Universal Installer or configuration assistant validates the response file at run time. If the validation fails, the silent mode installation or configuration process ends. Oracle Universal Installer treats values for parameters that are of the wrong context, format, or type as if no value was specified in the file.

Running DVCA After Creating a Database Vault Database

You should run Database Vault Configuration Assistant (DVCA) after creating a new Oracle Database Vault database, if any of the following conditions is true:

- Database Vault is installed into an Oracle home that has more than one database. You need to run DVCA on the other databases in the Oracle home. This enables Database Vault security for those databases. The databases should meet the prerequisites for installing Oracle Database Vault, as discussed in ["Preinstallation and Installation Tasks"](#) on page 2-1.
- Database Configuration Assistant (DBCA) is used to create a new Database Vault database in an Oracle home that already has a Database Vault database. DVCA loads the Database Vault schema objects into the new database, creates the DV_OWNER and optional DV_ACCTMGR accounts, and deploys the Database Vault Administrator application for the database.

Use the following syntax to run the DVCA utility:

```
$ORACLE_HOME/bin/dvca -action option [-racnode host_name] -oh oracle_home
-jdbc_str jdbc_connection_string -sys_passwd SYS_password -owner_account
DV_owner_account_name -owner_passwd DV_owner_account_password [-acctmgr_account
DV_account_manager_account_name] [-acctmgr_passwd DV_account_manager_password]
[-logfile ./dvca.log] [-silent] [-nodecrypt] [-lockout] [-languages
{"en"}, {"de"}, {"es"}, {"fr"}, {"it"}, {"ja"}, {"ko"}, {"pt_BR"}, {"zh_CN"}, {"zh_TW"}]}
```

Where:

- **action:** The action to perform. **option** creates the Database Vault schema objects, creates the DV_OWNER account and the optional DV_ACCTMGR account, and deploys the Database Vault Administrator application.
- **racnode:** The host name of the Oracle Real Application Clusters (Oracle RAC) node on which the action is being performed. Do not include the domain name with the host name. Use this option if this is a Oracle RAC database.
- **oh:** The Oracle home for the database.
- **jdbc_str:** The JDBC connection string used to connect to the database. For example, `jdbc:oracle:oci:@orcl1`, where `orcl1` is the net service name in the `tnsnames.ora` file (`$ORACLE_HOME/network/admin/tnsnames.ora`).
- **sys_passwd:** Password for user SYS. The command prompts for the password, if you do not enter it on the command line.
- **owner_account:** Oracle Database Vault Owner account name

-
- `owner_passwd`: Oracle Database Vault owner account password. The command prompts for the password, if you do not enter it on the command line.
 - `acctmgr_account`: (Optional) Oracle Database Vault Account Manager user
 - `acctmgr_passwd`: Oracle Database Vault Account Manager password (if a user name has been specified). The command prompts for the password, if you do not enter it on the command line.
 - `logfile`: Optionally, specify a log file name and location. You can enter an absolute path or a path that is relative to the location of the `$ORACLE_HOME/bin` directory
 - `silent`: Required if you are not running DVCA in an xterm window
 - `nodecrypt`: Reads plaintext passwords as passed on the command line. You must use this option if you are passing plaintext passwords to the command.
 - `lockout`: Disables SYSDBA operating system authentication
 - `languages`: Declares the language content to load, defaults to "en" (English). You can specify multiple languages. Include each language in quotation marks with commas separating different languages. Enclose the list of languages in braces. For example, `-languages {"en", "fr", "ja"}`.

The following lists the language key:

- `de`: German
- `en`: English
- `es`: Spanish
- `fr`: French
- `it`: Italian
- `ja`: Japanese
- `ko`: Korean
- `pt_BR`: Brazilian Portuguese
- `zh_CN`: Simplified Chinese
- `zh_TW`: Traditional Chinese

Note:

- If the Oracle system identifier (SID) of the database is more than 8 characters, then you would need to update the Net service name in the `tnsnames.ora` file before running DVCA. See *Oracle Database Vault Release Notes for Solaris Operating System (x86-64)* for more information.
-
-

Upgrading from a Previous Version of Database Vault

If you have Oracle Database Vault 10g Release 2 (10.2.0.2), Oracle Database Vault 10g Release 2 (10.2.0.3), or Oracle Database Vault 10g Release 2 (10.2.0.4) installed, then you can upgrade it to Oracle Database Vault 10g Release 2 (10.2.0.5) without uninstalling the existing instance.

Upgrading from a 10.2.0.x Version

Use the following steps to upgrade an Oracle Database Vault 10.2.0.x installation to Oracle Database Vault 10g Release 2 (10.2.0.5):

1. Re-create the password file with the `nosysdba=n` and `force=y` flags, to allow the SYS user to connect AS SYSDBA. Use the following syntax:

```
orapwd file=$ORACLE_HOME/dbs/orapwSID password=password force=y nosysdba=n
```

Here *SID* is the Oracle system identifier (SID) of the database and *password* is the password for the SYS account.

2. Shut down the database.

To stop a single-instance database, use the following commands:

```
sqlplus SYS "AS SYSDBA"  
Enter password:  
SQL> shutdown immediate
```

For an Oracle Real Application Clusters (Oracle RAC) database, use the following command:

```
$ORACLE_HOME/bin/srvctl stop database -d db_name -c "SYS/password AS SYSDBA"
```

Here *db_name* is the name of the database.

3. Relink the Oracle executable to turn off the Oracle Database Vault option. Use the following commands:

```
cd $ORACLE_HOME/rdbms/lib  
make -f ins_rdbms.mk dv_off  
cd $ORACLE_HOME/bin  
relink oracle
```

Note: For an Oracle Real Application Clusters (Oracle RAC) database, you must repeat the preceding commands on all nodes.

4. Start the database. For a single-instance database, use the following commands:

```
sqlplus SYS "AS SYSDBA"  
Enter password:  
SQL> startup
```

For an Oracle Real Application Clusters (Oracle RAC) database, use the following command:

```
$ORACLE_HOME/bin/srvctl start database -d db_name
```

5. Unlock the DVSYS account as the SYS user:

```
sqlplus SYS "AS SYSDBA"  
Enter password:  
SQL>ALTER USER DVSYS ACCOUNT UNLOCK;
```

6. Run Oracle Database Vault Configuration Assistant (DVCA) by using the `dvca -action disable` option. This disables the Database Vault triggers. Use the following syntax:

```
dvca -action disable  
      -service service_name  
      -owner_account DV_owner_account_name  
      [-logfile ./dvca.log]  
      [-nodecrypt] [-racnode host_name]
```

```
Enter SYS password: sys_password  
Enter owner password: owner_password
```

Here:

- `-action` is the action to perform. In this case the action is `disable`.
 - `-service` is the database service name.
 - `-owner_account` is the Oracle Database Vault Owner account name.
 - `-logfile` is an optional flag to specify a log file name and location. You can enter an absolute path, or enter a path that is relative to the location of the `$ORACLE_HOME/bin` directory.
 - `-nodecrypt` is the option to read plaintext passwords.
 - `-racnode` is the host name of the Oracle RAC node on which the action is performed. Use this option only in an Oracle RAC environment.
7. Install the Oracle Database Release 10.2.0.5 Patch Set.

See Also: ["Apply Oracle Database Release 10.2.0.5 Patch Set"](#) for more information about installing the patch set

8. Restart the database. For a single-instance database, use the following commands:

```
sqlplus SYS "AS SYSDBA"  
Enter password:  
SQL> shutdown immediate  
SQL> startup
```

For an Oracle Real Application Clusters (Oracle RAC) database, use the following command:

```
$ORACLE_HOME/bin/srvctl stop database -d db_name
```

```
$ORACLE_HOME/bin/srvctl start database -d db_name
```

9. Connect AS SYSDBA and run the following SQL statements:

```
SQL> DECLARE
    CURSOR stmt IS
        select u.name, o.name, r.pname
           from user$ u, obj$ o, rls$ r
        where u.user# = o.owner#
          and r.obj# = o.obj#
          and bitand(r.stmt_type,65536) > 0;

        object_schema VARCHAR2(32) := NULL;
        object_name VARCHAR2(32) := NULL;
        policy_name VARCHAR2(32) := NULL;

    BEGIN
        OPEN stmt;
        LOOP
            FETCH stmt INTO object_schema, object_name,
policy_name;

            EXIT WHEN stmt%NOTFOUND;
            dbms_ols.drop_policy(''||object_schema||'',
            '||object_name||'',
            '||policy_name||');
        END LOOP;
        Close stmt;
    END;
/
```

10. Run DVCA to reconfigure Database Vault. Use the following syntax:

```
$ORACLE_HOME/bin/dvca -action option -oh oracle_home -hostname host_name
-jdbc_str jdbc_connection_string -owner_account DV_owner_account_name
[-acctmgr_account DV_account_manager_account_name]
[-logfile ./dvca.log] [-nodecrypt] [-racnode node]
```

Where:

- **action:** The action to perform. *option* creates the Database Vault schema objects, creates the DV_OWNER account and the optional DV_ACCTMGR account, and deploys the Database Vault Administrator application.
- **oh:** The Oracle home for the database.
- **hostname:** The physical or virtual host name of the host on which the action is performed.
- **jdbc_str:** The JDBC connection string used to connect to the database. For example, `jdbc:oracle:oci:@orcl1`, where `orcl1` is the net service name in the `tnsnames.ora` file (`$ORACLE_HOME/network/admin/tnsnames.ora`).
- **owner_account:** Oracle Database Vault Owner account name
- **acctmgr_account:** (Optional) Oracle Database Vault Account Manager user
- **logfile:** Optionally, specify a log file name and location. You can enter an absolute path or a path that is relative to the location of the `$ORACLE_HOME/bin` directory

- **nodecrypt:** Reads plaintext passwords as passed on the command line. You must use this option if you are passing plaintext passwords to the command.
- **racnode:** The host name of the Real Application Clusters (Oracle RAC) node on which the action is being performed. Do not include the domain name with the host name. Use this option if this is an Oracle RAC database.

Note: You are prompted to enter the SYS, Database Vault Owner, and Database Vault Account Manager passwords.

See Also: [Appendix C, "Running DVCA After Creating a Database Vault Database"](#) for more options available with the `dvca -action` option command

- 11.** Run Oracle Database Vault Configuration Assistant (DVCA) by using the `dvca -action enable` option. This enables the Database Vault triggers. Use the following syntax:

```
dvca -action enable
      -service service_name
      -owner_account DV_owner_account_name
      [-logfile ./dvca.log]
      [-nodecrypt]
      [-racnode node]
```

```
Enter SYS password: sys_password
Enter owner password: owner_password
```

See Step 6 for details of the options used in the command.

- 12.** Lock the DVSYS account. Use the following SQL statements:

```
SQL> CONNECT SYS "AS SYSDBA"
Enter password:
SQL> ALTER USER DVSYS ACCOUNT LOCK;
```

- 13.** Shut down the database.

To stop a single-instance database, use the following commands:

```
sqlplus SYS "AS SYSDBA"
Enter password:
SQL> shutdown immediate
```

For an Oracle Real Application Clusters (Oracle RAC) database, use the following command:

```
$ORACLE_HOME/bin/srvctl stop database -d db_name
```

Here *db_name* is the name of the database.

- 14.** Relink the Oracle executable to turn on the Oracle Database Vault option. Use the following commands:

```
cd $ORACLE_HOME/rdbms/lib
make -f ins_rdbms.mk dv_on
cd $ORACLE_HOME/bin
relink oracle
```

Note: For an Oracle Real Application Clusters (Oracle RAC) database, you must repeat the preceding commands on all nodes.

- 15.** Start the database. For a single-instance database, use the following commands:

```
sqlplus SYS "AS SYSDBA"  
Enter password:  
SQL> startup
```

For an Oracle Real Application Clusters (Oracle RAC) database, use the following command:

```
$ORACLE_HOME/bin/srvctl start database -d db_name
```

- 16.** If you wish to disable connections with SYSDBA privileges, then re-create the password file with the `nosysdba=y` and `force=y` flags. Use the following syntax:

```
orapwd file=$ORACLE_HOME/dbs/orapwSID password=password force=y nosysdba=y
```

Here *SID* is the Oracle system identifier (SID) of the database and *password* is the password for the SYS account.

Database Listener Security Recommendations

This appendix lists the security recommendations for protecting the database listener.

Security Checklist for the Database Listener

The following configuration guidelines help enhance the security for your database listener:

- The database listener configuration file, `listener.ora`, and the supporting OracleNet configuration file, `tnsnames.ora`, should have the `ADMIN_RESTRICTIONS_LISTENER_SID=ON` protection enabled.
- The database listener configuration file, `listener.ora`, and the supporting OracleNet configuration file, `tnsnames.ora`, should have the `PLSExtProc` listener disabled.
- The listener should be configured to listen on a non-standard port. This means that the default port (1521) should be changed.
- The listener should be password protected or leverage operating system (OS) authentication based on the organizational security policy.
- The listener should use a unique name, which should be different from the default name.

- The `listener.ora` file should have the following parameter set:

```
INBOUND_CONNECT_TIMEOUT_ListenerName = 10
```

- The `sqlnet.ora` file should have the following parameters set:

```
SQLNET.INBOUND_CONNECT_TIMEOUT = 12  
SQLNET.EXPIRE_TIME = 10
```

- The listener should have logging enabled as follows:

```
LOGGING_LISTENER = ON  
LOG_STATUS = ON  
LOG_DIRECTORY_ListenerName = Directory_owned_by_Oracle_account  
LOG_FILE_ListenerName = File_owned_by_Oracle_account
```

Note: Only the owner and the DBA group should have permissions over the LOG_DIRECTORY. The owner should have read and write access to the LOG_DIRECTORY and the DBA group should have read access to it.

Only the owner and the DBA group should have read and write permissions over the LOG_FILE.

- The listener should have tracing enabled as follows:

```
TRACE_DIRECTORY_ListenerName = Directory_owned_by_Oracle_account
TRACE_FILE_ListenerName = File_owned_by_Oracle_account
TRACE_LEVEL = user
TRACE_FILELEN_ListenerName = 512
TRACE_FILENO_ListenerName = 1000
TRACE_TIMESTAMP_ListenerName = dd-mon-yyyy hh:mi:ss:mi
```

Note: Only the owner and the DBA group should have read and write permissions over the TRACE_DIRECTORY.

Only the owner and the DBA group should have read and write permissions over the TRACE_FILE.

Initialization Parameters

When you install Oracle Database Vault, the security specific database initialization parameters are initialized with default values. The following list shows the default values for these security specific initialization parameters:

```
REMOTE_LOGIN_PASSWORDFILE = default, EXCLUSIVE
AUDIT_SYS_OPERATIONS = TRUE
REMOTE_OS_AUTHENT = FALSE
REMOTE_OS_ROLES = FALSE
OS_ROLES = FALSE
OS_AUTHENT_PREFIX = ''
SQL92_SECURITY = TRUE
O7_DICTIONARY_ACCESSIBILITY = FALSE
```

Enabling Oracle Database Vault Administrator Accessibility

As part of the effort to make Oracle products, services, and supporting documentation accessible and usable to the disabled community, Oracle Database Vault Administrator offers several features that make management data available to users of assistive technology. To enable these features and provide for full accessibility, you must modify two configuration settings, which are described in the following sections:

- [Enabling Oracle Database Vault Administrator Accessibility Mode](#)
- [Providing Textual Descriptions of Database Vault Administrator Charts](#)

Enabling Oracle Database Vault Administrator Accessibility Mode

Oracle Database Vault Administrator takes advantage of user interface development technologies that improve the responsiveness of some user operations. For example, when you navigate to a new record set in a table, Oracle Database Vault Administrator does not redisplay the entire HTML page. However, this performance-improving technology is generally not supported by screen readers. To disable this feature, and as a result, make the Database Vault Administrator HTML pages more accessible for disabled users, use the following procedure.

To enable the display of an entire HTML page:

1. Locate the `uix-config.xml` configuration file.

To locate the `uix-config.xml` file in an Oracle Database 10g installation, change directory to the following location in the Oracle home:

```
$ORACLE_HOME/dv/jlib/dva_webapp/dva_webapp/WEB-INF/
```

2. Open the `uix-config.xml` file using a text editor and locate the following entry:

```
<!-- An alternate configuration that disables accessibility features -->
<default-configuration>
  <accessibility-mode>inaccessible</accessibility-mode>
</default-configuration>
```

3. Change the value of the `accessibility-mode` property from `inaccessible` to `accessible`.
4. Save and close the `uix-config.xml` file.
5. Restart Database Vault Administrator.

See Also: For more information on starting Oracle Database Vault Administrator, refer to *Oracle Database Vault Administrator's Guide*.

Providing Textual Descriptions of Database Vault Administrator Charts

In the Monitor page of the Database Vault Administrator, a chart is used to display security policy data. However, charts do not convey information in a manner that can be read by a screen reader. To remedy this problem, you can configure Database Vault Administrator to provide a complete textual representation of each chart. By default, support for the textual representation of charts is disabled. When textual description for charts is enabled, Database Vault Administrator displays a textual representation of the chart data.

To enable the textual representation of charts:

1. Locate the `web.xml` configuration file.

To locate the `web.xml` file in a Oracle Database 10g installation, change directory to the following location in the Oracle home:

```
$ORACLE_HOME/dv/jlib/dva_webapp/dva_webapp/WEB-INF/
```

2. Open the `web.xml` file with your favorite text editor and locate the following six lines of the file:

```
<!-- Uncomment this to enable textual chart descriptions
<context-param>
<param-name>enableChartDescription</param-name>
<param-value>true</param-value>
</context-param>
-->
```

3. Remove comments from this section by deleting the first line and the last line of this section so that the section consists of only these four lines:

```
<context-param>
<param-name>enableChartDescription</param-name>
<param-value>true</param-value>
</context-param>
```

4. Save and exit the `web.xml` file.
5. Restart Database Vault Administrator.

See Also: For more information on starting Oracle Database Vault Administrator, refer to *Oracle Database Vault Administrator's Guide*.

Index

Numerics

10.2.0.5 patch set, 2-9

A

accessibility features, G-1

accounts

Database Vault Account Manager, 1-2

Database Vault Owner, 1-1

unauthenticated access to, 2-18

ANONYMOUS user

unauthenticated account access with, 2-18

applying 10.2.0.5 patch set, 2-9

architecture

checking system architecture, 2-3

ASM. *See* Automatic Storage Management (ASM)

assistive technology, G-1

audit policy, 1-2

authorized problem analysis report

See APAR

Automatic Storage Management (ASM)

SYSDBA privilege, impact on, 2-19

B

backups

after upgrading, 2-17

importance, 2-9

preparing a strategy, 2-9

Bash shell

default user startup file, 2-12

.bash_profile file, 2-12

Bourne shell

default user startup file, 2-12

C

C shell

default user startup file, 2-12

certification, hardware and software, 1-2

change passwords

for oracle-supplied accounts, 2-17

checking

database requirements, 2-8

hardware requirements, 2-2

software requirements, operating system

requirements, 2-3

configuring

kernel parameters, 2-6

oracle user environment, 2-12

crsctl command, 2-11

CSD

download location for WebSphere MQ

on Solaris, 2-6

custom profiles, disable, 2-10

D

database (Oracle RAC)

starting, 2-19

database requirements, 2-8

Database Vault

accounts, 1-1

audit policy, 1-2

initialization parameters, 1-2

Database Vault Account Manager account, 1-2

password, 1-2

user name, 1-2

Database Vault Administrator (DVA) application

timeout value, 2-20

Database Vault Owner account, 1-1

password, 1-1

user name, 1-1

default file mode creation mask

setting, 2-12

deinstalling Oracle Database Vault, 2-23

disk space

checking, 2-3

DISPLAY environment variable

setting, 2-12, 2-13

DV_ACCTMGR role, 1-2

DV_OWNER role, 1-1

dvca command, C-1

E

Enterprise Manager Console DB

installing, 2-8

env command, 2-14

environment

checking settings, 2-14

configuring for oracle user, 2-12

environment variables
 DISPLAY, 2-12, 2-13
 ORACLE_BASE, 2-12
 ORACLE_HOME, 2-12, 2-14
 ORACLE_SID, 2-12
 PATH, 2-12
 removing from shell startup file, 2-12
 SHELL, 2-12
 TEMP and TMPDIR, 2-13
 TMP and TMPDIR, 2-3
 TNS_ADMIN, 2-14

errors
 silent mode, B-4
 /etc/oraInst.loc file, B-2, B-5
 /etc/system file, 2-7, 2-8

F

file mode creation mask
 setting, 2-12

files
 .bash_profile, 2-12
 editing shell startup file, 2-12
 /etc/oraInst.loc, B-5
 /etc/system, 2-7, 2-8
 .login, 2-12
 .profile, 2-12
 response files, B-2

H

hardware and software certifications, 1-2
hardware certification, 1-2
hardware requirements, 2-2

I

initialization parameters, 1-2, F-1

installation
 considerations, 1-2
 errors
 silent mode, B-4
 response files, B-1, B-2
 preparing, B-2
 silent mode, B-4
 templates, B-2
 silent mode, B-4
 error handling, B-5

installation types
 disk space requirements, 2-3

installing
 Enterprise Manager Console DB, 2-8
 Oracle Universal Installer, using, 2-14

instance
 instance identifier (SID), 2-12

instfix command, 2-5

J

Java
 font package requirements for Solaris, 2-4

JDK
 font packages required on Solaris, 2-4

K

kernel parameters
 checking on Solaris, 2-7
 configuring, 2-6
 making changes persist on Solaris, 2-7, 2-8

Korn shell
 default user startup file, 2-12

L

listener, 2-8
 security checklist, E-1

logging on
 SYSDBA privilege connections, disabling, 2-18

.login file, 2-12

M

mask
 setting default file mode creation mask, 2-12

memory requirements, 2-2

mode
 setting default file mode creation mask, 2-12

monitoring
 accessibility features, enabling, G-2
 textual representation in charts, enabling, G-2

multiple Oracle homes, 1-2

O

operating system
 checking version of Solaris, 2-4

operating system requirements, 2-3

Oracle Clusterware
 starting, 2-11

Oracle Database
 setting ORACLE_SID environment variable, 2-12

Oracle Database Vault
 audit policy, 1-2
 deconfiguring, 2-23
 deinstalling, 2-23
 initialization parameters, 1-2, F-1
 remove, 2-23
 uninstalling, 2-23

Oracle Database Vault Administrator
 accessibility features, enabling, G-1

Oracle Database Vault Administrator (DVA)
 deploying manually
 to Database Console OC4J container, 2-22
 to standalone OC4J container, 2-20

Oracle homes, multiple, 1-2

Oracle Real Application Clusters (Oracle RAC)
 SYSDBA privilege, impact on, 2-19

Oracle software owner user
 configuring environment for, 2-12
 determining default shell, 2-12

Oracle Universal Installer, 2-8, 2-9, 2-14

- response files, B-1
- oracle user
 - configuring environment for, 2-12
 - determining default shell, 2-12
- ORACLE_BASE environment variable
 - removing from shell startup file, 2-12
 - setting, 2-12
- ORACLE_HOME environment variable
 - removing from shell startup file, 2-12
 - unsetting, 2-14
- ORACLE_SID environment variable
 - removing from shell startup file, 2-12
 - setting, 2-12
- oracle-supplied accounts
 - change passwords, 2-17
- orapwd utility, 2-18
- OUI, 2-9

P

- packages
 - checking on Solaris, 2-4
- password file, 2-8
- passwords
 - Database Vault Account Manager, 1-2
 - Database Vault Owner, 1-1
 - password files, 2-18
 - resetting
 - with SQL*Plus, 2-17
 - specifying for response files, B-1
 - unlocking
 - with SQL*Plus, 2-17
 - See also* security
- patch set
 - applying, 2-9
 - documentation, 2-9
- patchadd command, 2-6
- patches
 - download location for Solaris, 2-6
- PATH environment variable
 - setting, 2-12
- pkginfo command, 2-4
- process
 - stopping existing, 2-11
- processor
 - checking system architecture, 2-3
- .profile file, 2-12
- program technical fix
 - See* PTF

R

- RAM requirements, 2-2
- reboot command, 2-7
- remote SYSDBA connections
 - disabling, 2-18
- REMOTE_LOGIN_PASSWORDFILE parameter, 2-8
- requirements
 - database, 2-8
 - hardware, 2-2

- listener, 2-8
- Oracle Database 10.2.0.5 patch set, 2-9
- Oracle Enterprise Manager Console DB
 - 10.2.0.5, 2-8
- password file, 2-8
- software, operating system, 2-3
- response files
 - about, B-1
 - general procedure, B-2
 - passing values at command line, B-1
 - passwords, B-1
 - security, B-1
 - specifying with Oracle Universal Installer, B-4
 - See also* silent mode, B-1
- response files installation
 - about, B-1
- roles
 - DV_ACCTMGR, 1-2
 - DV_OWNER, 1-1

S

- security
 - See also* passwords
- security checklist
 - database listener, E-1
- seminfo_semmni parameter
 - recommended value on Solaris, 2-6, 2-7
- seminfo_semmns parameter
 - recommended value on Solaris, 2-6
- seminfo_semmsl parameter
 - recommended value on Solaris, 2-6, 2-7
- seminfo_semvmx parameter
 - recommended value on Solaris, 2-6
- semni parameter
 - recommended value on Solaris, 2-6, 2-7
- semns parameter
 - recommended value on Solaris, 2-6
- semmsl parameter
 - recommended value on Solaris, 2-6, 2-7
- semvmx parameter
 - recommended value on Solaris, 2-6
- shell
 - determining default shell for oracle user, 2-12
- SHELL environment variable
 - checking value of, 2-12
- shell startup file
 - editing, 2-12
 - removing environment variables, 2-12
- shminfo_shmmax parameter
 - recommended value on Solaris, 2-6, 2-7
- shminfo_shmmin parameter
 - recommended value on Solaris, 2-6
- shminfo_shmmni parameter
 - recommended value on Solaris, 2-6, 2-7
- shminfo_shmsegs parameter
 - recommended value on Solaris, 2-6
- shmmax parameter
 - recommended value on Solaris, 2-6, 2-7
- shmmin parameter

- recommended value on Solaris, 2-6
- shmmni parameter
 - recommended value on Solaris, 2-6, 2-7
- shmseg parameter
 - recommended value on Solaris, 2-6
- SID
 - setting ORACLE_SID environment variable, 2-12
- silent mode installation, B-4
- software and hardware certifications, 1-2
- software certification, 1-2
- software requirements, operating system requirements, 2-3
- Solaris
 - checking kernel parameters, 2-7
 - checking version, 2-4
 - font packages for Java, 2-4
 - making kernel parameter changes persist, 2-7, 2-8
 - patch download location, 2-6
- svrctl command, 2-19
- startup file
 - for shell, 2-12
- stopping
 - Oracle processes, 2-11
- swap space
 - checking, 2-2
 - requirements, 2-2
- SYSDBA remote connections
 - disabling, 2-18
- sysdef command, 2-7
- system architecture
 - checking, 2-3
- system file, 2-7, 2-8

T

- TEMP environment variable
 - setting, 2-13
- temporary disk space
 - requirements, 2-2
- TMP environment variable, 2-3
- TMPDIR environment variable, 2-3
 - setting, 2-13
- TNS_ADMIN environment variable
 - unsetting, 2-14

U

- umask, 2-14
- umask command, 2-12, 2-14
- uname command, 2-4
- uninstalling Oracle Database Vault, 2-23
- UNIX commands, 2-14
 - env, 2-14
 - instfix, 2-5
 - patchadd, 2-6
 - pkginfo, 2-4
 - reboot, 2-7
 - sysdef, 2-7
 - umask, 2-12
 - uname, 2-4

- unset, 2-14
- unsetenv, 2-14
- unset command, 2-14
- unsetenv command, 2-14
- upgrading
 - after upgrading, 2-16
 - backup strategy, 2-9
 - post upgrade actions, 2-16
 - previous Database Vault version, D-1
- user names
 - Database Vault Account Manager, 1-2
 - Database Vault Owner, 1-1
- users
 - Database Vault Account Manager, 1-2
 - Database Vault Owner, 1-1

W

- WebSphere MQ
 - CSD download location
 - for Solaris, 2-6