

# **Oracle Tuxedo for IBM i 6.1**

Users Guide

Oracle Tuxedo 10gR3

April 2010

**ORACLE®**

Copyright © 2007, 2010, Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this software or related documentation is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, the following notice is applicable:

U.S. GOVERNMENT RIGHTS Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, duplication, disclosure, modification, and adaptation shall be subject to the restrictions and license terms set forth in the applicable Government contract, and, to the extent applicable by the terms of the Government contract, the additional rights set forth in FAR 52.227-19, Commercial Computer Software License (December 2007). Oracle USA, Inc., 500 Oracle Parkway, Redwood City, CA 94065.

This software is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications which may create a risk of personal injury. If you use this software in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure the safe use of this software. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software in dangerous applications.

Oracle is a registered trademark of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners.

This software and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

Interoperability 1  
The Installation Process 1  
Before You Begin 2  
Installing from a Microsoft Windows Platform 2  
Installing from a UNIX System Platform 4  
Creating a Profile for a Oracle Tuxedo Administrative Group 1  
Granting Special Authority 2  
Setting the Correct Time Offset 2  
User Interface and IBM i 6.1 Concepts 1  
Invoking Programs from the Command Line 2  
Interactive and Batch Jobs 3  
HFS and IFS File Systems 3  
HFS 3  
IFS 3  
Commands for HFS and IFS Files 3  
Redirection of Standard IO and Standard Error 4  
Workarounds 4  
Examples 4  
Development Environment 5  
buildcvt Example 6  
buildsvr Example 6  
tmconfig 7  
epifreg 7  
viewc, viewc32 7  
Xerces-C++ Parser 7  
XML Encoding With EBCDIC Character 7  
IBM i 6.1 Command Names 7  
Runtime Environment 8  
Sample Application 9  
Shutting Down the Application 13  
IPC Resources 14  
Configuration Issues 15  
/Q 16  
Administration Console 16  
Jolt Relay 17

TxRPC 17  
/COBOL 18

# Installing the Oracle Tuxedo System on IBM i 6.1

This chapter contains the following topics:

- [Interoperability](#)
- [The Installation Process](#)

## Interoperability

Oracle Tuxedo 10g Release 3 (10.3) running on an IBM i 6.1 platform can interoperate, as either master or non-master, with 10g Release 3 (10.3) running on any other supported platform. Backward compatibility (that is, interoperability between 10g Release 3 (10.3) and prior releases) is supported only if the master node is running 10g Release 3 (10.3).

All workstation platforms that are currently supported work with this release.

**Note:** If remote domain is Oracle Tuxedo 6.5 on other OS, local domain on IBM i 6.1 must set environment variable whose name is `<remote domainid>ISOS400` to "n".

## The Installation Process

This section provides instructions for preparing your environment for the Oracle Tuxedo system, installing the Oracle Tuxedo system from a Microsoft Windows or UNIX system platform.

## Before You Begin

Before you start installing the Oracle Tuxedo system, sign on to your IBM i 6.1 system and make sure you have a user profile for Oracle Tuxedo installation. If you do not, create one now. The user defined in this profile will be the owner of all the program objects created during the installation process.

## Installing from a Microsoft Windows Platform

1. Oracle Tuxedo 10g Release 3 (10.3) for IBM i 6.1 is distributed in a .ZIP file. Before installation, extract this file to any directory and then start the next installation.
2. Create a 3-line file containing the following ftp information:

```
open IBM i 6.1-machine-name  
account-name  
password
```

For example, suppose that (a) you are working on an IBM i 6.1 machine called lc400b.oracle.com, (b) your login is rtl, and (c) your password is rtl123. Your profile contains the following three lines:

```
open lc400b.oracle.com  
rtl  
rtl123
```

This file is used to automatically execute the pre-installation procedures necessary for installing Oracle Tuxedo 10g Release 3 (10.3) through ftp. Once the pre-installation steps are completed, the file should be removed.

**Note:** A new line is required after the password line.

3. Invoke the pre-installation batch file, preinst.bat, with the appropriate command-line arguments.

```
preinst.bat pkgdir tmpdir tuxdir tuxlib filename
```

where:

- `pkgdir` is the extracted ZIP file directory.
- `tmpdir` is the library on the IBM i 6.1 machine in which copies of the Oracle Tuxedo save files will be stored.
- `tuxdir` is the IFS file system on the IBM i 6.1 machine on which the Oracle Tuxedo system will be installed.

- `tuxlib` is the library on the IBM i 6.1 machine where the saved files are restored.
- `filename` is the full path to a file that contains ftp account and password information for the IBM i 6.1 machine on which the Oracle Tuxedo system is installed.

4. Run the install program on the IBM i 6.1 machine.

```
addlib tuxlib
call coreinst (tmplib tuxlib '/tuxdir'
'full|server|client|joltclt|atmiclt|jrly' 'y|n')
```

where you specify one of the following Oracle Tuxedo installation component packages:

- `full` (to install Oracle Tuxedo installation component packages)
- `server` (to install all Oracle Tuxedo server package)
- `client` (to install only the Oracle Tuxedo all client packages)
- `joltclt` (to install only the Oracle Tuxedo Jolt client)
- `atmiclt` (to install only the Oracle Tuxedo ATMI client)
- `jrly` (to install only the Oracle Tuxedo Jolt JRLY)

Specify one of the following for sample's installation:

- `'y'` (to install samples when package type is full or server.)
- `'n'` (do not install samples)

**Note:** The words `full`, `server`, `client`, `atmiclt`, `joltclt` and `jrly`, `y` and `n` must be entered in lowercase.

During the installation process (which may take several minutes), a number of restoring X to Y messages are displayed, such as the following.

```
restoring service programs to tuxlib
```

5. Remove all the saved files that were created in Step 3 from `tmplib`.

**Note:** Remove `tmplib`, too, if it is different from `tuxlib` and it is no longer needed.

6. Initialize the `tlisten` passwords. The `tlisten` password is used for authentication during the boot process of a multiple-node application. To initialize the password file, enter the following command.

```
call tlistpwd 'tuxdir'
```

where the value of `tuxdir` is the directory specified as `tuxdir` in Step 4. This command will prompt for passwords until a non-null password is entered. For further details about the password file, see `tlisten` in the Oracle Tuxedo Reference Manual.

7. Before using SSL, enter the following command to configure SSL:

```
addlib tuxlib
```

**Note:** `tuxlib`: The library on the IBM i 6.1 where the save files are restored.

```
call sslconf ('tuxdir' 'hostname' 'portid' 'baseobj' 'filename')
```

`tuxdir`: The IFS file system (on the IBM i 6.1) where Oracle Tuxedo is installed.

`hostname`: The URL of the LDAP server system.

`portid`: A port number for the URL of the LDAP server system.

`baseobj`: A base object for search in LDAP server.

`filename`: The name of LDAP filter file, if the input is " (null), the default value of "\$tuxdir/udataobj/security/bea\_ldap\_filter.dat" will be used.

8. Your installation of the Oracle Tuxedo system is now complete.

## Installing from a UNIX System Platform

1. Oracle Tuxedo 10g Release 3 (10.3) for IBM i 6.1 is distributed in a .ZIP file. Before installation, extract this file to any directory and then start the next installation.
2. Set up a `.netrc` file to allow ftp to sign on to the IBM i 6.1 machine. For example, suppose that (a) you are working on an IBM i 6.1 machine called `lc400b.oracle.com`, (b) your login is `rtl`, and (c) your password is `rtl123`. Your `.netrc` file will contain the following three lines.

```
machine lc400b.oracle.com
login rtl
password rtl123
```

3. Invoke the preinstallation shell, `preinst.sh`, with the appropriate command-line arguments:

```
preinst.sh mount-point tmlib tuxdir tuxlib machine, where:
```

- `mount-point` is the extracted ZIP file directory.
- `tmlib` is the library on the IBM i 6.1 where Oracle Tuxedo save files are located.
- `tuxdir` is the IFS file system (on the IBM i 6.1) where Oracle Tuxedo is installed.
- `tuxlib` is the library on the IBM i 6.1 where the save files are restored.
- `machine` is the name of the IBM i 6.1 machine where Oracle Tuxedo is installed.



4. Run the install program on the IBM i 6.1 machine.

```
addlib tuxlib
call coreinst (timplib tuxlib '/tuxdir'
'full|server|client|joltclt|atmiclt|jrly' 'y|n')
```

where you specify one of the following Oracle Tuxedo installation component packages:

- full (to install Oracle Tuxedo installation component packages)
- server (to install all Oracle Tuxedo server package)
- client (to install only the Oracle Tuxedo all client packages)
- joltclt (to install only the Oracle Tuxedo Jolt client)
- atmiclt (to install only the Oracle Tuxedo ATMI client)
- jrly (to install only the Oracle Tuxedo Jolt JRLY)

Specify one of the following for sample's installation:

- 'y' (to install samples when package type is full or server.)
- 'n' (do not install samples)

**Note:** The words full, server, client atmiclt, joltclt and jrly, y and n must be entered in lowercase.

During the installation process (which may take several minutes), a number of restoring X to Y messages will be displayed, such as.

```
restoring service programs to tuxlib
```

5. Remove all the saved files that were created in Step 3 from timplib.

**Note:** Remove timplib, too, if it is different from tuxlib and it is no longer needed.

6. Initialize the tlisten passwords. The tlisten passwords are used for authentication during the boot process of a multiple-node application. To initialize the password file, enter the following command.

```
call tlistpwd 'tuxdir'
```

where the value of tuxdir is the directory specified as tuxdir in Step 4. This command will prompt for passwords until a non-null password is entered. For further details about the password file, see tlisten in the Oracle Tuxedo Reference Manual.

7. Before using SSL, enter the following command to configure SSL:

```
addlib tuxlib
```

## Installing the Oracle Tuxedo System on IBM i 6.1

`tuxlib`: The library on the IBM i 6.1 where the save files are restored.

```
call sslconf ('tuxdir' 'hostname' 'portid' 'baseobj' 'filename')
```

`tuxdir`: The IFS file system (on the IBM i 6.1) where Oracle Tuxedo is installed.

`hostname`: The URL of the LDAP server system.

`portid`: A port number for the URL of the LDAP server system.

`baseobj`: A base object for search in LDAP server.

`filename`: The name of LDAP filter file, if the input is " (null), the default value of "\$tuxdir/udataobj/security/bea\_ldap\_filter.dat" will be used.

8. Your installation of the Oracle Tuxedo system is now complete.

# Configuration for Oracle Tuxedo System Administration

This chapter contains the following topics:

- [Creating a Profile for a Oracle Tuxedo Administrative Group](#)
- [Granting Special Authority](#)
- [Setting the Correct Time Offset](#)

## Creating a Profile for a Oracle Tuxedo Administrative Group

To set the group ID correctly for members of an administrative group, you must set up a group profile. A group profile is the same as a user profile except that the group ID number is set to a numeric value. Each user's profile can then refer (in the group profile field) to the group profile name.

For example, consider the user and group profiles for an administrator named Joe with a login ID of joe:

- In the user profile for user joe:
  - The group profile field (GRPPRF) is set to tuxadm.
  - The user ID number (UID) field is set to 6494.
- In the group profile for group tuxadm, the group ID number (GID) is set to 601.

If user joe runs the id utility as follows.

```
call id
```

then the following output is displayed on the screen.

```
uid = 6494, euid = 6494, gid = 601, egid = 601
```

User profiles and group profiles can be set up with the CRTUSRPRF command.

## Granting Special Authority

The user profile for an administrator must include \*JOBCTL special authority. This special authorization allows the Oracle Tuxedo system to bypass some security checks when it is trying to verify the state of the following:

- System processes within the Oracle Tuxedo system, and
- Clients being run under a user profile other than that of the administrator.

Without this authorization, the Oracle Tuxedo system fails to do the following:

- Restart servers and
- Clean up after clients should they fail to detach from an application when they exit or when they end unexpectedly.

You can add this authorization to your user profile by adding \*JOBCTL to the Special Authority (SPCAUT) list. To do so, complete the following tasks:

- Sign on as QSECOFR.
- Run the chgusrprf command.

## Setting the Correct Time Offset

In order for the Oracle Tuxedo Administration Console to work properly, the system variable QUTCOFFSET must be properly set. Use the wrksysval command to specify the offset (in hours and minutes) between the current system time and the Coordinated Universal Time (UTC), also known as Greenwich mean time. For example, in the Eastern Standard Time time zone, QUTCOFFSET should be set to +4 hours.

# Using the Oracle Tuxedo System on UNIX and IBM i 6.1 Platforms


This chapter contains the following topics:

- [User Interface and IBM i 6.1 Concepts](#)
- [Runtime Environment](#)

## User Interface and IBM i 6.1 Concepts

The user interface on an IBM i 6.1 system is completely menu-driven. The interface makes extensive use of function keys F1-F24.

Figure 3-1 Main Menu of Tasks for IBM i 6.1 Platform



## Invoking Programs from the Command Line

Virtually every action performed via the menu has a command-line equivalent. Application executables, such as Oracle Tuxedo utilities, can be invoked from the command line using the `call` command. The `call` command has the following syntax:

```
call pgm parm(arg1 arg2 . . . )
```

The notion of the `PATH` and `LD_LIBRARY_PATH` environment variables in the UNIX shell is replaced by the library list. For example, the following command:

```
call hello parm('world')
```

is a request to search in the library list for the `hello` program. The first library in the library list that contains this program becomes the current library and the `hello` program is activated.

During this activation, if a service program (the IBM i 6.1 equivalent of a DLL or shared object) is needed, then the library list is searched again. The library list can be displayed with the `dsplib` command, and manipulated with the `addlib` and `rmvlib` commands.

## Interactive and Batch Jobs

Jobs define execution context (roughly equivalent to a process). There are two kinds of jobs: interactive and batch. When a user signs on to a system, an interactive job is assigned to the new session. All call commands are executed inside this job. The `wrkactjob` command lists all active jobs on the system. (It is equivalent to the `ps` command on a UNIX system.) A batch job can be submitted via the `sbmjob` command. The `wrksbmjob` command lists all submitted batch jobs.

## HFS and IFS File Systems

This section describes the two file systems that are important on an IBM i 6.1 platform: HFS and IFS.

### HFS

HFS is the traditional flat file system. At the highest level it contains libraries. Each library may contain files, e.g., module files, program files, and physical files. A physical file, in turn, may contain members. All text files (including C program source code files) are stored as members of a physical file.

Executables may reside only in HFS, but symbolic links can be created from IFS to HFS via the `addlnk` command.

### Filenames

HFS filenames are limited to ten characters and are not case sensitive.

### IFS

IFS is a directory-oriented file system designed to support PC file-serving. IFS (especially /QOpenSys) closely resembles a UNIX file system.

Executables may reside only in HFS, but symbolic links can be created from IFS to HFS via the `addlnk` command.

### Filenames

With one exception (/QOpenSys) filenames in IFS are case sensitive.

## Commands for HFS and IFS Files

Separate commands must be used for HFS and IFS files:

- The `wrklib`, `wrkf`, and `wrkmbrpdm` commands work only with HFS objects.
- The `cd`, `mkdir`, `dspcurdir`, and `wrklnk` commands may be used with both IFS files and HFS files, but different syntax is required, depending on whether you are accessing HFS or IFS objects.
- The `cpytostmf` and `cpyfrmstmf` commands are available for copying a text file from one type of file system to another. For example, the following command copies an IFS file called `/QOpenSys/tuxedo/tmp/xyz` to an HFS physical file called `tmp` in a member called `xyz` (in a library called `apps`).

```
cpyfrmstmf fromstmf('/QOpenSys/tuxedo/tmp/xyz') +
tombr('/qsys.lib/tmp.file/xyz.mbr') +
mbropt(*replace)
```

## Redirection of Standard IO and Standard Error

When you are working with ILE C programs in an HFS file system, you may redirect standard input, standard output, and standard error (the `stdin`, `stdout`, and `stderr` files, respectively) by using the `ovrdbf` command. See the CL Reference Manual for details.

There is no simple way to redirect standard IO and standard error messages to and from IFS files.

### Workarounds

- To redirect to an IFS file you must first redirect to an HFS file and then copy the HFS file to an IFS file.
- To redirect from an IFS file you must first copy from an IFS file to an HFS file, and then redirect from the HFS file.

### Examples

For example, to redirect `stdout` of an ILE C program called `prog` to an IFS file called `/home/dougd/out`, enter the text shown in [Listing 3-1](#).

#### Listing 3-1 Redirection Example

---

```
ovrdbf file(stdout) tofile (tmplib/tmpfile) +
mbr (stdout)
call prog
cpytostmf frommbr +
```



```
( '/qsys.lib/tmplib.lib/tmpfile.file/stdout.mbr' ) +
tostmf ( '/home/dougd/out' ) stmfopt (*replace)
```

---

## Development Environment

The `make`, `lex`, and `yacc` utilities are not available on the IBM i 6.1. The native character set is EBCDIC, not ASCII.

Two Oracle Tuxedo commands, `buildclient` and `buildserver`, have been renamed `buildclt` and `buildsrvr`, respectively, in order to conform to the 10-character maximum.

The `buildclt` and `buildsrvr` commands accept input only for module files (`*MODULE`), service program files (`*SRVPGM`), binding directory (`*BNDDIR`), and produce output program files (`*PGM`). The ILE C modules must be produced by `crtcmmod`. Likewise, ILE COBOL modules must be produced by `crtcblmod`.

The following example command lines show how to compile a C source file in member `cx` of a file called `tuxsrc` in a library called `apps`. The object module is created in a file called `cx` in a library called `apps`.

```
crtcmmod module(apps/cx) srcfile(apps/tuxsrc) srcmbr(cx) +
sysifcopt(*ifsio) dbgview(*all) define('DEF=1')
```

Note that the special system interface option `sysifcopt(*ifsio)` is specified here. This option allows the C runtime library to access IFS files. Because the Oracle Tuxedo system is compiled with this option, we strongly recommend using it for compatibility.

Note also that debugging has been turned on by `dbgview(*all)` and the preprocessor defined for `DEF` has been set to 1. This is equivalent to specifying `-DDEF=1 -g` on a `cc` command line (on a UNIX platform).

Currently you cannot specify a C source file on the `buildclt` or `buildsrvr` command line.

The `-f` and `-l` options to the `buildclt` and `buildsrvr` commands also mean something slightly different from the same options to the equivalent commands (`buildclient` and `buildserver`) on a UNIX system.

On a UNIX platform, the `-f` (first) option allows you to specify a list of items to be passed to the `cc` command such that the objects produced by running `cc` on these items are linked before the Oracle Tuxedo libraries are linked.

The `-l` (last) option allows you to specify a list of items to be passed to the `cc` command such that the objects produced by running `cc` on these items are linked after the Oracle Tuxedo libraries are linked.

On an IBM i 6.1 platform the `-f` option accepts object modules (that is, files of type `*MODULE`) only, and the `-l` option accepts service programs (that is, files of type `*SVRPGM`) only.

The `-B` option allows you to specify a binding directory (`*BNDDIR`).

## buildclt Example

Consider the following example command line.

```
call buildclt ('-fapps/cx' '-fapps/cy' '-oapps/client')
```

This command accomplishes two tasks:

- It links two objects (`cx` and `cy`) in an HFS library called `apps`.
- It produces a client executable program called `client` in the `apps` library.

## buildsrvr Example

Consider the following example command line:

```
call buildsrvr ('-fapps/sx' '-fapps/sy' '-oapps/server' '-sSVC')
```

This command accomplishes two tasks:

- It links objects `sx` and `sy` in an HFS library (`apps`).
- It produces a server executable program (`server`) in a library (`apps`) which offers a service (`SVC`).

If the `-k` option of `buildsrvr` is used, then the server main code is generated in member `BSpid` of the `tuxsrc` file in the `qtemp` library, where the value of `pid` is the process ID of the `buildsrvr` process. Because the `qtemp` library is removed at the end of each job, you must make a copy of it in a permanent directory before signing off, if you want to keep it.

Both `mkfldhdr` and `viewc` generate header files in IFS, usually in the current directory. You must copy these `.h` files into an HFS `h` file so the C compiler will be able to find them.

The `mkfldhdr/ mkfldhdr32 -H` option creates a header file in HFS.

`viewc` also generates the binary output file with a `.vv` (instead of a `.v`) suffix.

## tmconfig

On the IBM i 6.1, the valid EDITOR environment variable values for `tmconfig` command are "STRSEU" and "EDTF". If editing lines longer than 240 characters is required, please use EDTF.

## epifreg

For the `epifreg` command `-f` option, the library name and service program name must be upper cased as shown in the following example:

```
call epifreg ('-r' '-p qa/fanatz1' '-i engine/security/authorization' '-o
SYSTEM' '-v 1.0' '-f AAA101/FANATZ1' '-e qa_atz_entry').
```

## viewc, viewc32

There is a difference in IBM i 6.1 and UNIX. If the `-c` option is specified, one COBOL copy file is created for each VIEW defined in the viewfile. These copy files are created in root directory (/), not in current directory like UNIX, unless an alternate directory is specified through the `-d` option.

## Xerces-C++ Parser

Because of the 10 characters limit, all include files for Xerces-C++ Parser are located only in IFS. So the source code that includes those header files should be copied to IFS, and set `INCLUDE` environment variable to `$TUXDIR/include` before compiles. For an introduce to programming with Xerces-C++ , see the Xerces-C++ Version 2.8.0 Programming Guide.

## XML Encoding With EBCDIC Character

If the XML buffer is encoded as EBCDIC characters, the encoding attribute should be set to "EBCDIC-CP-US".

## IBM i 6.1 Command Names

Because of the 10 characters limit some others Tuxedo commands are changed on IBM i 6.1.

**Table 3-1 IBM i 6.1 Command Names**

On Unix	On IBM i 6.1
tmloadrepos	tmldrep

**Table 3-1 IBM i 6.1 Command Names**

tmunloadrepos	tmunldrep
TMS_rac_refresh	TMS_racrf
snmp_integrator	snmpintgrt
snmp_version	snmp_ver
snmpgetnext	snmpgetn
reinit_agent	rinitagent

## Runtime Environment

The Oracle Tuxedo system is distributed with a set of tools for manipulating the environment: `getenv`, `putenv`, `setenv`, and `env`.

**Table 3-2 Command Syntax for Runtime Tools**

Syntax	Function
<code>getenv var</code>	Displays the value of the specified environment variable ( <code>var</code> )
<code>putenv 'var=value'</code>	Sets the specified environment variable ( <code>var</code> ) to the specified value ( <code>value</code> )
<code>setenv file</code>	Calls <code>putenv</code> on every line of the specified file ( <code>file</code> )
<code>env</code>	Displays the values of all variables in your environment

IBM i 6.1 provides a single command, `wrkenvvar`, that offers functionality similar to that available through `getenv`, `putenv`, `setenv`, and `env`. The `wrkenvvar` command differs from the Oracle Tuxedo commands, however, in several aspects. First, unlike the distributed tools delivered with the Oracle Tuxedo system, `wrkenvvar` cannot handle the expansion of variable names marked with a `$` prefix (similar to shell variable expansion).

In addition, the `hostname` and `id` utilities are distributed only with the Oracle Tuxedo system:

- The `hostname` command prints the name of the network node for the IBM i 6.1. The machine name used in the `UBBCONFIG` configuration file must match the name returned by `hostname`.

- The `id` command prints the UID and GID of the current user profile. The UID and GID values specified in the `UBBCONFIG` configuration file must match the values returned by the `id` command. (See [Chapter 2, “Configuration for Oracle Tuxedo System Administration,”](#))

All Oracle Tuxedo executables and header files are packaged in an HFS library (see `tuxlib` during installation). Other data files (such as `udataobj/*` and `locale/C/*`) are placed in `$TUXDIR` in IFS. `$TUXDIR/bin` has symbolic links to HFS executables. `$APPDIR` should also reside in IFS. You must add the HFS library to the library list before invoking any Oracle Tuxedo commands.

## Sample Application

Assume `tuxdir` is installed in `/QOpenSys/tuxedo`, `tuxlib` is installed as `Tuxedo`, and `APPDIR` is set to `/home/apps/simpapp`.

Begin by building the `simpcl` and `simperv` programs (in Steps 1-9).

1. Create an HFS library called `apps`.

```
crplib apps
```

2. Create a physical source file called `tuxsrc`.

```
crtsrcpf apps/tuxsrc rcdlen (120)
```

3. Copy `simpcl.c` from `/qopensys/tuxedo/samples/atmi/simpapp` to `tuxsrc` `simpcl` member.

```
cpyfrmstmf fromstmf('/qopensys/tuxedo/samples/atmi/simpapp/simpcl.c') +
tombr('/qsys.lib/apps.lib/tuxsrc.file/simpcl.mbr') +
mbropt(*replace)
```

4. Generate a client object module by running the ILE C compiler.

```
crtcmod module(apps/simpcl) srcfile(apps/tuxsrc) +
srcmbr(simpcl) sysifcopt(*ifsio)
```

5. Generate a client program by running `buildclt`.

```
call buildclt ('-fapps/simpcl' '-oapps/simpcl')
```

6. Copy `simperv.c` from `/qopensys/tuxedo/apps/simpapp` to member `simperv` of `tuxsrc`.

```
copyfirmstmf fromstmf('/qopensys/tuxedo/samples/atmi/simpapp/simpserv.c') +
tombr('/qsys.lib/apps.lib/tuxsrc.file/simpserv.mbr') +
mbropt(*replace)
```

7. Generate a server object module by running the ILE C compiler.

```
crtcmbr module(apps/simpserv) srcfile(apps/tuxsrc) +
srcmbr(simpserv) sysifcopt(*ifsio)
```

8. Generate a server program by running the `buildsrvr` command.

```
call buildsrvr ('-sTOUPPER' '-fapps/simpserv' '-oapps/simpserv')
```

9. Create a symbolic link from `/home/apps/simpapp/simpserv` to `apps/simpserv`.

```
addlnk obj('/qsys.lib/apps.lib/simpserv.pgm') +
newlink('/home/apps/simpapp/simpserv')
```

10. Add `tuxlib` to the library list.

```
addlible tuxedo
```

11. Set the necessary environment variables as follows.

```
call putenv 'TUXDIR=/QOpenSys/tuxedo'
call putenv 'APPDIR=/home/apps/simpapp'
call putenv 'PATH=/QOpenSys/tuxedo/bin:/home/apps/simpapp'
```

12. Create the `TUXCONFIG` file from the `UBBCONFIG` configuration file `UBBCONFIG`.

```
call putenv 'TUXCONFIG=$APPDIR/tuxconfig'
call tmloadcf ('-y' 'UBB')
```

13. Run `wrklnk` to verify that the file `tuxconfig` has been created in `/home/apps/simpapp`.

14. Boot the application.

```
call tmboot '-y'
```

Messages similar to those shown in [Figure 3-2](#) are displayed.

Figure 3-2 Messages Displayed at Boot Time

```

Session A - [24 x 80]
File Edit View Communication Actions Window Help
Server Id = 0 Group Id = simple Machine = simple: shutdown succ
eeded
2 processes stopped.
Press ENTER to end terminal session.
Booting all admin and server processes in /home/apps/simpapp/tuxconfig
INFO: Oracle Tuxedo, Version 10.3.0.0, 32-bit, Patch Level 028

Booting admin processes ...

exec BBL -A :
    process id=420073 ... Started.

Booting server processes ...

exec simpserv -A :
    process id=420074 ... Started.
2 processes started.
Press ENTER to end terminal session.

==> _

F3=Exit F4=End of File F6=Print F9=Retrieve F17=Top
F18=Bottom F19=Left F20=Right F21=User Window

20/007
Session successfully started

```

15. Now run the client by entering a command such as the following.

```
call apps/simpcl 'abc'
```

Figure 3-3 shows the messages that are displayed.

Figure 3-3 Messages Displayed after the Client Is Called

```
Session A - [24 x 80]
File Edit View Communication Actions Window Help

2 processes stopped.
Press ENTER to end terminal session.
Booting all admin and server processes in /home/apps/simpapp/tuxconfig
INFO: Oracle Tuxedo, Version 10.3.0.0, 32-bit, Patch Level 028

Booting admin processes ...

exec BBL -A :
    process id=420073 ... Started.

Booting server processes ...

exec simpserv -A :
    process id=420074 ... Started.
2 processes started.
Press ENTER to end terminal session.
Returned string is: ABC
Press ENTER to end terminal session.

==>

F3=Exit F4=End of File F6=Print F9=Retrieve F17=Top
F18=Bottom F19=Left F20=Right F21=User Window

a 20/007
IBM - Session successfully started
```

16. View the userlog file (which was created in \$APPDIR in IFS) on IBM i 6.1 with EDTF as shown in [Figure 3-4](#).



Figure 3-4 Viewing the Userlog File with EDTF

```

Session A - [27 x 132]
File Edit View Communication Actions Window Help
Browse : /home/apps/simpapp/UL06.032910
Record : 1 of 8 by 18 Column : 1 121 by 131
Control :

.....1.....2.....3.....4.....5.....6.....7.....8.....9.....0.....1.....2.....3.
*****Beginning of data*****
175400.DENNLAS1.MLAB.JOEDWARDS.COM:IBL.420660.0X00000E10.0: 03-29-2010: client high water (0), total client (0)
175400.DENNLAS1.MLAB.JOEDWARDS.COM:IBL.420660.0X00000E10.0: 03-29-2010: Tuxedo Version 10.3.0.0, 32-bit, Patch Level 020
175400.DENNLAS1.MLAB.JOEDWARDS.COM:IBL.420660.0X00000E10.0: LIBTUX_CAT:262: INFO: Standard main starting
175409.DENNLAS1.MLAB.JOEDWARDS.COM:SIMPSERV.420604.0X00000E10.0: 03-29-2010: Tuxedo Version 10.3.0.0, 32-bit
175409.DENNLAS1.MLAB.JOEDWARDS.COM:SIMPSERV.420604.0X00000E10.0: LIBTUX_CAT:262: INFO: Standard main starting
175409.DENNLAS1.MLAB.JOEDWARDS.COM:SIMPSERV.420604.0X00000E10.0: Welcome to the simple server
175409.DENNLAS1.MLAB.JOEDWARDS.COM:SIMPSERV.420604.0X00000E10.0: simple server enter sleep
175423.DENNLAS1.MLAB.JOEDWARDS.COM:SIMPSERV.420604.0X00000E10.0: rqst->data: ABC
*****End of Data*****

F3=Exit F10=Display Hex F12=Cancel F15=Services F16=Repeat find F19=Left F20=Right
03/012
Session successfully started

```


## Shutting Down the Application

To shut down an application, enter the following command.

```
call tmshtutdown '-y'
```

Figure 3-5 shows the messages displayed during the shutdown process.

Figure 3-5 Messages Displayed During Shutdown

A screenshot of a terminal window titled "Session A - [24 x 80]". The window contains the following text:

```
process id=420884 ... Started.  
2 processes started.  
Press ENTER to end terminal session.  
Returned string is: ABC  
Press ENTER to end terminal session.  
Shutting down all admin and server processes in /home/apps/simpapp/tuxconfig  
  
Shutting down server processes ...  
  
Server Id = 1 Group Id = GROUP1 Machine = simple:      shutdown succ  
eeded  
  
Shutting down admin processes ...  
  
Server Id = 0 Group Id = simple Machine = simple:      shutdown succ  
eeded  
2 processes stopped.  
Press ENTER to end terminal session.  
  
==> _____  
  
F3=Exit F4=End of File F6=Print F9=Retrieve F17=Top  
F18=Bottom F19=Left F20=Right F21=User Window
```

The terminal window also shows a status bar at the bottom with "20/007" and "MP a" on the left, and "MP1900 - Session successfully started" at the very bottom.

## IPC Resources

IBM ships a set of IPC tools as a PTF. These tools provide the functionality available on a UNIX system through the `ipcs` and `ipcrm` commands. There are some differences, however, the IBM tools have different names and produce output in a different manner.

To view the IPC resources consumed by all your applications, enter the following command.

```
call qp0zipcs
```

The output of `qp0zipcs` is generated in `*QPRINT` which means that it can be viewed as a spool file with the `wrksp1f` command.

To remove a particular IPC resource, such as a message queue ID (`qid`), enter the following command.

```
call qp0zipcr ('-qqid')
```

When an error occurs while you are running `qp0zipcr`, a message is generated in the `joblog`. Use the `dspjoblog` command to view it.

## Configuration Issues

- Server names are case-sensitive if \$APPDIR is in /QOpenSys.
- Servers must reside in IFS under \$APPDIR. These IFS files must be symbolic links to the HFS PGM files. (Use the `addlnk` command to create a symbolic link.) The IFS name must be identical to the HFS name; thus each IFS name is restricted to 10 characters.
- The machine name must be a string returned by the `hostname` command.
- The `tlisten` command does not start itself in the background. To submit a batch job with `tlisten`, use the `sbmjob` command, for example:

```
Addlible tuxlib
Addenvvar envvar('TUXDIR') value('/QOpenSys/tuxedo')
SBMJOB CMD(CALL PGM(TLISTEN) PARM('-l' '//hostname:8899'))
JOB(TLISTEN) CPYENVVAR(*YES).
```

- Because a TCP/IP socket is used, no BRIDGE device needs to be specified.
- The RCMD parameter to be executed on a server when the latter is restarted must refer to a symbolic link in \$PATH, typically \$APPDIR. This symbolic link must point to an executable program in HFS. UNIX shell scripts will not work here.
- Due to the difference between the collating sequences in EBCDIC and ASCII, ranges specified for data-dependent routing may not behave the same way on IBM i 6.1 and UNIX platforms.
- DDR for decimal is not supported.
- On an IBM i 6.1 platform, a superuser (QSECOFR) cannot perform Oracle Tuxedo administrative tasks. For example, you cannot boot an application while signed on as QSECOFR. Therefore Oracle Tuxedo administrators must not sign on as QSECOFR.
- Effective blocktime values are rounded up to the nearest `SCANUNIT*2-1` value.
- The field type of ptr (a pointer to a buffer) is not supported in FML32.
- The `tpusr` file is required for AUTHSVR.

## /Q

The threshold command parameter specified on the `qmadmin qcreate` command line (such as the server RCMD), must refer to a symbolic link to an executable program in HFS. The link must be included in `$PATH`; typically it is found in `$APPPDIR`.

UNIX shell scripts will not work here.

## Administration Console

With Oracle Tuxedo 10g Release 3 (10.3), you can administer an Oracle Tuxedo application through any Web browser (such as Netscape or Internet Explorer) by using the Web-based GUI for administration. This section provides some tips for running the Oracle Tuxedo Administration Console on an IBM i 6.1 platform.

Three files `$TUXDIR/udataobj/webgui/webguitop.html`, `$TUXDIR/udataobj/tuxwsvr.ini`, and `$TUXDIR/udataobj/webgui.ini` need to be modified. For example:

- Replace "`TUXDIRVALUE`" in file `$TUXDIR/udataobj/webgui/webguitop.html` with the value of `TUXDIR`.
- Replace "`http://HOST/cgi-bin/tuxadm`" in file `$TUXDIR/udataobj/webgui/webguitop.html` with "`/cgi-bin/tuxadm`".
- Replace "`<TUXDIR>`" in file `$TUXDIR/udataobj/tuxwsvr.ini` with the value of `TUXDIR`.
- Replace "`<TUXDIR>`" in file `$TUXDIR/udataobj/webgui/webgui.ini` with the value of `TUXDIR`.
- Replace "`<LOCAL_HOST>`" in `$TUXDIR/udataobj/webgui/webgui.ini` with the host name.

Two programs, `tuxwsvr` and `wlisten`, need to be run in the background. This can be accomplished by using `sbmjob` like `tlisten`. For example:

```
addlib tuxlib
addenvvar envvar('TUXDIR') value('/QOpenSys/tuxedo')
SBMJOB CMD(CALL PGM(tuxwsvr) PARM('-l' '//hostname:8899' '-i'
'TUXDIR/udataobj/tuxwsvr.ini')) JOB(tuxwsvr) CPYENVVAR(*YES)
```

Current implementation also requires that for all user CGI programs, the HFS library in which they reside be added to the library list.

The procedure for setting up a batch job with `wlisten` is similar to setting up a batch job for `tuxsvr` or `tlisten`.

To start the Administration Console for Oracle Tuxedo administration on the IBM i 6.1, enter the following URL.

`http://machine_name:port/webguitop.html` (where `machine_name:port` is the IBM i 6.1 machine/port combination on which `tuxsvr` is running).

For additional information on preparing to use the Oracle Tuxedo Administration Console, refer to Starting the Oracle Tuxedo Administration Console in the Oracle Tuxedo Installation Guide.

## Jolt Relay

The combination of the Jolt Relay (JRLY) and its associated Jolt Relay Adapter (JRAD) is typically referred to as the Internet Relay. Jolt Relay routes messages from a Jolt client to a JSL or JSH. This eliminates the need for the JSH and Oracle Tuxedo to run on the same machine as the Web server (which is generally considered insecure).

The program JRLY need to be run background. This can be accomplished by using `sbmjob` or `sbmdbContext` like `tlisten` or `tuxsvr`.

For additional information on Jolt Relay refer to Oracle Jolt.

## TxRPC

By default, the `tidl` compiler does not run the C preprocessor. This means that if you have `#define` statements or any other pre-processor constructs in the input file, then you will need to specify the `-cpp_cmd` option:

```
call tidl ('-cpp_cmd' 'crtcmmod' . . . )
```

By default, the `tidl` command also produces server and client stub files in the current IFS directory. The stub files are named `x_cstub.c` and `x_sstub.c`. It is also possible to generate stub files in HFS by using the `-out` option to specify a library in the directory `/qsys.lib`, as in the following example:

```
call tidl ('-out' '/qsys.lib/tuxedo.lib' . . . )
```

In this case, the stub files will be generated in the physical file `idl` with members named `x_cs` and `x_ss` for client and server stubs, respectively. The `tidl` command also generates a header file in the current working directory of IFS. For example, if the `idl` compiler is run on input file `x.idl` as follows:

```
call tidl ('-cpp_cmd' 'crtcmmod' '-keep' 'c_source' 'x.idl')
```

then tidl will generate the following three files in the current working directory of IFS:

- x\_cstub.c
- x\_sstub.c
- x.h

In addition, the tidl compiler will copy the header file to member x belonging to file h in the qtemp library.

If the -keep option is not specified, then the C compiler will be invoked on the stub files to produce object modules x\_cs and x\_ss in library qtemp. (qtemp is the default output library which can be overridden by the -out option, as described earlier.)

## /COBOL

The Oracle Tuxedo system supports clients and servers written in the ILE COBOL language. The major differences between MicroFocus COBOL and ILE COBOL are listed below.

- The ILE COBOL compiler does not allow tabs in source code; use spaces whenever possible.
- The COMP-5 data type is COMP-4 in ILE COBOL.

The command-line interface for ILE COBOL must use the linkage section rather than the ACCEPT statement.

The method of redirecting output to a file is different. Consult the COBOL Programmer's Guide and COBOL reference manuals for details. Two applications shipped with the Oracle Tuxedo system (CSIMPAPP and STOCKAPP) also show how some tasks are performed on an IBM i 6.1 platform.

You can override the Oracle Tuxedo TMDISPATCH9 ( ) to TMDISPATCH16 ( ) for COBOL routines only when set environment variable TM\_COB\_STATIC to YES before create COBOL program.