

SeeBeyond™ eBusiness Integration Suite

CGI Web Server e*Way Intelligent Adapter User's Guide

Release 4.5.2

Java Version



The information contained in this document is subject to change and is updated periodically to reflect changes to the applicable software. Although every effort has been made to ensure the accuracy of this document, SeeBeyond Technology Corporation (SeeBeyond) assumes no responsibility for any errors that may appear herein. The software described in this document is furnished under a License Agreement and may be used or copied only in accordance with the terms of such License Agreement. Printing, copying, or reproducing this document in any fashion is prohibited except in accordance with the License Agreement. The contents of this document are designated as being confidential and proprietary; are considered to be trade secrets of SeeBeyond; and may be used only in accordance with the License Agreement, as protected and enforceable by law. SeeBeyond assumes no responsibility for the use or reliability of its software on platforms that are not supported by SeeBeyond.

e*Gate, e*Insight, e*Way, e*Xchange, e*Xpressway, eBI, iBridge, Intelligent Bridge, IQ, SeeBeyond, and the SeeBeyond logo are trademarks and service marks of SeeBeyond Technology Corporation. All other brands or product names are trademarks of their respective companies.

© 2002 by SeeBeyond Technology Corporation. All Rights Reserved. This work is protected as an unpublished work under the copyright laws.

This work is confidential and proprietary information of SeeBeyond and must be maintained in strict confidence.

Version 20021010085257.

Contents

Chapter 1

Introduction	8
Overview	8
Intended Reader	8
Components	9
Supported Operating Systems	10
System Requirements	10

Chapter 2

Installation	11
Supporting Documents	11
Installing the CGI Web Server e*Way	11
Windows NT and Windows2000	12
Pre-installation	12
UNIX	12
Pre-installation	12
Files/Directories Created by the Installation	14

Chapter 3

Configuration	16
Configuring the Participating Host Components in the Enterprise Manager	16
Multi-Mode e*Way Configuration Parameters	18
Multi-Mode e*Way Configuration	18
JVM Settings	19
JNI DLL Absolute Pathname	19
CLASSPATH Prepend	20
CLASSPATH Override	20
CLASSPATH Append From Environment Variable	21
Initial Heap Size	21
Maximum Heap Size	21
Maximum Stack Size for Native Threads	21
Maximum Stack Size for JVM Threads	21
Disable JIT	22

Remote Debugging port number	22
Suspend option for debugging	22
Auxiliary JVM Configuration File	22
Configuring the Web Server Components	23
Configuring Apache Web Server	23
Configuring IIS Web Server	24
Configuring iPlanet Web Server	26
Modifying the mscgi.properties File	28
JMS Connection Section	28
CGI Data Section	29
Log Section	31
Hex Dump vs. Text Dump	31

Chapter 4

Implementation 33

The Request/Reply Model	33
Request/Reply and the CGI Web Server e*Way Participating Host Components	33
The Request/Reply Sample	34
e*Gate Request/Reply Sample Set up	34
Sample Functionality	35
ewwebRequestETDReplyETD	35
Event Type Definitions	36
webRequestETD	37
Node Descriptions	37
webReplyETD	42
Node Description	43
Collaboration Rules and the CGI Web Server Header	45
Test HTML Files	50
testmultptfrm.html	51
testurlencoded.html	52
Message Routing to Multiple Collaborations	53

Chapter 5

Methods 55

CGI Java e*Way Methods	55
Class Hierarchy	55
Class Body	55
Body	56
getRawPayload	56
setRawPayload	56
getTransferCodePayload	57
setTransferCodePayload	57
getTextStringPayload	58
setTextStringPayload	58
marshal	58
unmarshal	59
Class NameValue	59
NameValue	60

getName	60
getValue	60
setIsURLEncoded	61
marshal	61
unmarshal	62
Class OneMimeBodyPart	62
OneMimeBodyPart	63
getMimeBodyPart	63
getMimeBodyPartRawPayLoad	63
setMimeBodyPartRawPayLoad	64
getMimeBodyPartDecodedPayLoad	64
getMimeBodyPartTextStringPayLoad	65
setMimeBodyPartTextStringPayLoad	65
isMimeBodyPart	65
isMimeType	66
getDisposition	66
setDisposition	67
setContentID	67
getContentID	68
getContentTypeString	68
setContentMD5	68
getContentMD5	69
getDescription	69
setDescription	70
getEncoding	70
getFileName	70
setFileName	71
getContentType	71
countNestedMultiPart	72
getNestedMultiPart	72
marshal	72
unmarshal	73
Class OneMimeBodyPart.NestedMultiPart	73
OneMimeBodyPart.NestedMultiPart	74
setCurrIndex	74
getSize	74
getPart	75
unmarshal	75
Class webReplyETD	76
webReplyETD	76
getJMSReplyTo	76
setJMSReplyTo	77
send	77
getBody	78
getContentType	78
addHeader	79
setHeader	79
getHeader	79
getMultiParts	80
isMultipart	80
countMultiParts	81
marshal	81
Class webRequestETD	82
webRequestETD	82
getJMSReplyTo	82
getContentType	83
getRequestMethod	83
getEnvironmentVariables	84
countEnvironmentVariables	84
getURLNameValueQueryPairs	85
isSingleBody	85

getBody	85
isUrlencoded	86
countURLNameValueQueryPairs	86
getMultiParts	87
isMultipart	87
countMultiParts	87
unmarshal	88
Class webETDContentType	88
webETDContentType	89
unmarshal	89
toString	89
getPrimaryType	90
setPrimaryType	90
getSubType	91
setSubType	91
getCharSet	91
setCharSet	92
getMultipartBoundary	92
setMultipartBoundary	93
getContentTransferEncoding	93
setContentTransferEncoding	93
getContentTypeParameter	94
setContentTypeParameter	94
marshal	95
Class webETDInternetHeaders	95
webETDInternetHeaders	95
addHeader	96
setHeader	96
getHeader	97
getAsInternetHeaders	97
marshal	97
Class webReplyETD.ReplyMultiParts	98
webReplyETD.ReplyMultiParts	98
setCurrIndex	98
getSize	99
getPart	99
marshal	100
Class webRequestETD.EnvironmentVariables	100
webRequestETD.EnvironmentVariables	100
setCurrIndex	101
addEnvVarPair	101
getSize	101
getName	102
getValue	102
Class webRequestETD.MultiParts	103
webRequestETD.MultiParts	103
setCurrIndex	103
getSize	104
unmarshal	104
getPart	104
Class webRequestETD.URLNameValueQueryPairs	105
webRequestETD.URLNameValueQueryPairs	105
getSize	105
getName	106
getValue	106
setCurrIndex	107
unmarshal	107

Index

Introduction

This chapter provides an overview of SeeBeyond™ Technology Corporation's (SeeBeyond™) CGI Web Server e*Way Intelligent Adapter.

1.1 Overview

The CGI Web Server e*Way acts as a gateway to the e*Gate system for a Web server. Normally, a Web server is limited to sharing local data sources only. The CGI Web Server e*Way allows the Web server to access remote data sources which would otherwise be unavailable. The CGI Web Server e*Way makes a variety of data sources available through the e*Way system.


The CGI Web Server e*Way is comprised of two components, the Web server component and the Participating Host component. The Web server component resides in a Web server's CGI-bin directory. This executable, stccgi.exe, can be considered a generic CGI executable, in that it can be used with a variety of Web servers that utilize CGI. It parses CGI input supplied by a Web server using either the GET or POST method, packages the input along with the Web server's environment variables, and sends the packaged message to the Participating Host component residing on a machine where an e*Gate Participating Host is running. The Participating Host component forwards the message to the e*Gate backend system for processing. After sending the message, the Web server component waits for a reply from the Participating Host component and, upon receipt of the response, sends the response message to the Web server which can then deliver the message to the requesting Web client (for example, a browser).

For additional details, see [Chapter 4](#).

1.1.1. Intended Reader

The reader of this guide is presumed to be a developer or system administrator with responsibility for maintaining the e*Gate system; to have working knowledge of operations and administration for the specific operating systems under which the Web server and e*Gate run; to be familiar with CGI; and to be familiar with Windows-style GUI operations.

Figure 1 Overview of the CGI Web Server e*Way implementation



1.1.2. Components

The CGI Web Server e*Way is comprised of the following:

- **Web server components** (the CGI Web Server e*Way client) which consists of the Web server component executable and supporting library files
- **Participating Host components** (the CGI Web Server e*Way server) consisting of a Multi-mode e*Way and a JMS e*Way Connection

A complete list of installed files appears in [Table 1 on page 14](#).

1.2 Supported Operating Systems

The CGI Web Server e*Way is available on the following operating systems:

- Windows 2000, Windows 2000 SP1, Windows 2000 SP2, and Windows SP3
- Windows NT 4.0 SP6a
- Solaris 2.6, 7, and 8
- AIX 4.3.3
- HP-UX 11.0 and HP-UX 11i
- Red Hat Linux 6.2
- Japanese Windows 2000, Windows 2000 SP1, and Windows 2000 SP2, and Windows SP3
- Japanese Windows NT 4.0 SP6a
- Japanese Solaris 2.6, 7, and 8
- Japanese HP-UX 11.0

1.3 System Requirements

To use the CGI Web Server e*Way, you need the following:

- An e*Gate Participating Host, version 4.5.1 or later.
- In addition to the disk space required by e*Gate, additional disk space is required to process and queue the data that this e*Way processes; the amount necessary will vary based on the type and size of the data being processed, and any external applications performing the processing.
- A TCP/IP network connection

The Web server that communicates with the CGI Web Server e*Way requires a client system with the following:

- A Web server, such as:
 - ♦ Apache Web Server
 - ♦ iPlanet Web Server
 - ♦ MSIS Web Server
- Sufficient memory and disk space to support Web server functions. See the CGI Web server user's guides for more information regarding server requirements.

Note: *The e*Gate Participating Host may optionally host the Web server, but is not required to do so.*

Installation

This chapter covers the installation requirements for the CGI Web Server e*Way and the Web server component configuration. A list of the files and directories created by the installation is also provided.

2.1 Supporting Documents

The following documents provide additional information that may be useful in conjunction with the *CGI Web Server e*Way Intelligent Adapter User's Guide*.

- *Creating an End-to-end Scenario with e*Gate Integrator*
- *e*Gate Integrator Alert Agent User's Guide*
- *e*Gate Integrator Alert and Log File Reference Guide*
- *e*Gate Integrator Collaboration Services Reference Guide*
- *e*Gate Integrator Installation Guide*
- *e*Gate Integrator Intelligent Queue Services Reference Guide*
- *e*Gate Integrator SNMP Agent User's Guide*
- *e*Gate Integrator System Administration and Operations Guide*
- *e*Gate Integrator User's Guide*
- *Standard e*Way Intelligent Adapters User's Guide*
- *Readme.txt* file on the e*Gate installation CD-ROM.

2.2 Installing the CGI Web Server e*Way

When installing this e*Way as part of a complete e*Gate installation, follow the instructions in the *e*Gate Integrator Installation Guide*. The CGI Web Server e*Way is installed as an "Add-on" component in the fourth phase of the installation. To add the CGI Web Server e*Way to an existing e*Gate installation, follow the proceeding instructions.

2.3 Windows NT and Windows2000

Before installing e*Gate on your Windows NT or 2000 system, read the following sections to ensure a smooth and error-free installation.

2.3.1. Pre-installation

- Exit all programs before running the setup program, including any anti-virus applications.
- Administrator privileges are required to install this e*Way.

To install the CGI Web Server e*Way on a Windows NT or Windows 2000 system

- 1 Log in as Administrator to the workstation on which the e*Way is to be installed.
- 2 Close any open applications.
- 3 Launch the setup application on the e*Gate installation CD-ROM.
- 4 Follow the online prompts in the InstallShield® Wizard. When the **Select Components** dialog box appears, clear all the check boxes except **Add-ons**. Click **Next** as necessary to proceed through the setup application.
- 5 When the **User Information** dialog box appears, type your name and company name.
- 6 When the **Choose Destination Location** window appears, **do not** change the **Default Destination** folder unless you are directed to do so by SeeBeyond support personnel; simply click **Next** to continue.
- 7 When the **Select Components** dialog box appears, select **eWays**, click the **Change..** button, and select **CGI Web Server e*Way**.

After the installation is complete, reboot the computer and launch the Enterprise Manager.

2.4 UNIX

Before installing the e*Way on your UNIX system, read the following sections to ensure a smooth and error-free installation.

2.4.1. Pre-installation

- Exit all programs before running the setup program, including any anti-virus applications.
- Root privileges are not required to install the e*Way.

To install the CGI Web Server e*Way on a UNIX system

- 1 Log onto the workstation on which the e*Way will be installed. If not logged in as root, you must have sufficient privileges to install files in the “egate” directory tree.
- 2 Insert the CD-ROM into the drive.
- 3 If necessary, mount the CD-ROM drive. See the *e*Gate Integrator Installation Guide* for information on mounting the CD-ROM on a particular UNIX systems.
- 4 At the shell prompt, type
cd /cdrom/setup
- 5 Start the installation script by typing:
setup.sh
- 6 If not logged in as root, a message is displayed stating that services do not start automatically for non-root users. Press **Enter** to continue.
- 7 A message appears to confirm that the e*Gate installation script is running, and note that typing - (hyphen) backs up a step, or **QUIT** (all capitals) exits the install program. Press **Enter** to continue.
- 8 When prompted to accept the license agreement, type **y** and press **Enter**.
- 9 The platform type and a menu of options is displayed:

```
Installation type (choose one):  
0. Finished with installation.  Quit.  
1. e*Gate Addon Applications  
2. e*Gate Participating Host (Client)  
3. e*Gate Registry Server
```

Type 1 to select the **e*Gate Add-on Applications** and press **Enter**.

- 10 When prompted for the installation path, press **Enter** to accept the default path, or enter a new path and press **Enter**.
 - When logged in as root, the suggested path is **/opt/egate/client**.
 - When logged in under any other user name, the suggested path is **/home/username/egate/client**.

Whether installing e*Gate to an application directory such as **/opt** to a **/home** directory, it is strongly recommend that the recommended relative path “egate/client” be used as the destination directory for the add-on-application installation.

- 11 When prompted, type **U** to update (overwrite) and press **Enter**.

Note: *U* updates the installation and overwrites files as necessary. *M* creates a directory and moves everything in the current directory to *directoryname.old*.

If “**U**” is selected a warning appears regarding shared EXE and DLL files. Read the warning and press **Enter** to continue.

- 12 Enter the name of the Registry Server that supports the add-on applications. If the installation utility detects a Registry Host running on the current server, suggests that host’s name.

- 13 A prompt appears for the **administration login** (an e*Gate user with sufficient privilege to create components within a schema). The default is **Administrator**; unless you have created a different “administrative” user name, press **Enter** to accept the default. The default password is listed in the README.TXT file in the root directory of the installation CD-ROM.
- 14 Enter and confirm the password for the user specified in the step above.

*Note: e*Gate user names and passwords are case-sensitive.*

- 15 A menu of add-on options appears. Type the number corresponding to the desired add-on package (**CGI Web Server e*Way**) and press **Enter**.
- 16 Follow the on-screen instructions to complete the installation.
- 17 After the add-on application has been installed, the **Choose add-on packages** menu appears. Repeat step 15 to install additional packages, or **0** and press **Enter** to continue.
- 18 When the **Installation Type** menu appears the Add-on applications installation is complete. Do one of the following:
 - ♦ To exit the setup utility, type **0** and press **Enter**.
 - ♦ To continue the installation select another option .

2.5 Files/Directories Created by the Installation

The CGI Web Server e*Way installation process installs the following files within the e*Gate directory. Files are installed within the “egate\client” tree on the Participating Host and committed to the “default” schema on the Registry Host.

Table 1 Server-side files installed

e*Gate Directory	File(s)
client\bin\	stccgi.exe
client\classes\	Stccgi.jar
client\ThirdParty\gnu-getopt\	gnu-getopt.jar
client\ThirdParty\jaf\jaf-1.0.1\	activation.jar
client\ThirdParty\javamail\javamail-1.2\	mailapi.jar

Table 2 lists the files that must be manually copied onto the system running the Web server.

Table 2 Client-side files installed

Client Directory	File(s)
On IIS: \inetpub\scripts\ On Apache: \ApacheGroup\Apache\cgi-bin\ On iPlanet: \NetScape\Server4\cgi-bin\	stc_msclient.dll stc_mscommon.dll stc_msapi.dll stccgi.exe

Table 3 lists the sample files that must be copied from the Installation CD manually to the Web server scripts directory:

Table 3 Sample files :

Installation CD	File(s)
\samples\ewcgi\Java\	mscgi.properties readme.txt testmulptfrm.html testurlencoded.html webETD_CGI.zip

Sample files do NOT install automatically. They must be copied from the Installation CD to a temporary location. See [Configuring the Web Server Components](#) on page 23 and [The Request/Reply Sample](#) on page 34 for more information.

Note: *After installation, change the file permissions to allow the Web server to read and execute these files.*

Configuration

3.1 Configuring the Participating Host Components in the Enterprise Manager

Important


From the perspective of the e*Gate GUIs, the CGI e*Way is not a system of components distributed between the Web server and a Participating Host, but a single component that runs an executable file (the **stccgi.exe**). When this manual discusses procedures within the context of any e*Gate GUI, the term “e*Way” refers only to the Participating Host component of the CGI e*Way system.

Configuring the Participating Host components

- 1 If you have not already done so, launch the Enterprise Manager.
- 2 Verify that the IQ Manager Type is set to SeeBeyond JMS.


Since the stccgi.exe publishes Events to JMS, the IQ Manager type in your Participating Host must be set to SeeBeyond JMS.

Figure 2 SeeBeyond JMS IQ Manager




- 3 Create and configure an e*Way Connection. The connection type should be set to "SeeBeyond JMS". (For the sample, the e*Way Connection is referred to as "cpBackstayJMS".)

Figure 3 e*Way Connection



In the configuration file, the Connection Type should be set to "Topic", since the sample is using the Publish/Subscribe model.

Figure 4 Connection Type



The server name is the computer name on which the JMS Server (SeeBeyond JMS IQ Manager) is running. This is also the machine on which the Participating Host is installed. The Host name is the same as the server name.

- 4 Using the Components editor, create a new e*Way.
- 5 Display the new e*Way's properties.
- 6 On the **General** tab, under **Executable File**, click **Find** and select **stceway.exe**.
- 7 Click **OK** to close the properties dialog box, or continue to configure the e*Way. Configuration parameters are discussed in [Chapter 3](#). The setup and requirements of schemas using the stceway.exe e*Way are discussed in [Chapter 4](#).
- 8 Each e*Way has a Collaboration associated with it. Each Collaboration must have an associated source/destination.

Note: Once the e*Way is installed and configured, it must be incorporated into a schema by defining and associating the appropriate Collaborations, Collaboration Rules, IQs, and Event Types before the e*Way can perform its intended function. For more

information about any of these procedures, please see the online Help system.

For more information about configuring e*Ways or using the e*Way Editor, see the *e*Gate Integrator User's Guide*.

3.1.1. Multi-Mode e*Way Configuration Parameters

e*Way configuration parameters are set using the e*Way Editor.


3.2 Multi-Mode e*Way Configuration

Multi-Mode e*Way properties are set using the Enterprise Manager.

To create and configure a New Multi-Mode e*Way:

- 1 Select the Navigator's Components tab.
- 2 Open the host and control broker on which you want to create the e*Way.
- 3 On the Palette, click on the **Create a New e*Way** button.
- 4 The New e*Way Component window opens. Enter the name of the new e*Way, then click **OK**.
- 5 Right-click the new e*Way and select **Properties** edit its properties.

Figure 5 Multi-Mode e*Way Properties



- 6 When the e*Way Properties window opens, click on the **Find** button beneath the **Executable File** field, and select an executable file. For the purposes of the sample select **stceway.exe** (**stceway.exe** is located in the "bin\" directory).
- 7 Under the **Configuration File** field, click on the **New** button. When the Settings page opens, set the configuration parameters for this configuration file.

- 8 After selecting the desired parameters, save the current configuration. Close the `.cfg` file and select **OK** to close the e*Way Properties Window.

The Multi-Mode e*Way configuration parameters are found in the following section:

3.2.1. JVM Settings

The JVM Settings control basic Java Virtual Machine settings.

- [JNI DLL Absolute Pathname](#) on page 19
- [CLASSPATH Prepend](#) on page 20
- [CLASSPATH Override](#) on page 20
- [CLASSPATH Append From Environment Variable](#) on page 21
- [Initial Heap Size](#) on page 21
- [Maximum Heap Size](#) on page 21
- [Maximum Stack Size for Native Threads](#) on page 21
- [Maximum Stack Size for JVM Threads](#) on page 21
- [Disable JIT](#) on page 22
- [Remote Debugging port number](#) on page 22
- [Suspend option for debugging](#) on page 22
- [Auxiliary JVM Configuration File](#) on page 22

JNI DLL Absolute Pathname

Description

Specifies the absolute pathname to where the JNI DLL installed by the *Java 2 SDK 1.3* is located on the Participating Host.

Required Values

A valid pathname.

Additional Information

The JNI dll name varies on different O/S platforms:

OS	Java 2 JNI DLL Name
Windows NT 4.0/ Windows 2000	jvm.dll
Solaris 2.6, 2.7, 2.8	libjvm.so
OS/390	libjvm.so
HP-UX	libjvm.sl
AIX 4.3.3 and 5.1	libjvm.a

The value assigned may contain a reference to an environment variable. To do this, enclose the variable name within a pair of % symbols. For example:

```
%MY_JNIDLL%
```

Such variables are used when multiple Participating Hosts are used on different platforms.

Note: *To ensure that the JNI DLL loads successfully, the Dynamic Load Library search path environment variable must be set appropriately to include all the directories under the Java 2 SDK (or JDK) installation directory that contain shared libraries (UNIX) or DLLs (NT).*

CLASSPATH Prepend

Description

Specifies the paths to be prepended to the CLASSPATH environment variable for the JVM.

Required Values

An absolute path or an environmental variable. This parameter is optional.

Additional Information

If left unset, no paths are prepended to the CLASSPATH environment variable.

Existing environment variables may be referenced in this parameter by enclosing the variable name in a pair of % signs. For example:

```
%MY_PRECLASSPATH%
```

CLASSPATH Override

Description

Specifies the complete CLASSPATH variable to be used by the JVM. This parameter is optional. If left unset, an appropriate CLASSPATH environment variable (consisting of required e*Gate components concatenated with the system version of CLASSPATH) is set.

Note: *All necessary JAR and ZIP files needed by both e*Gate and the JVM must be included. It is advised that the **CLASSPATH Prepend** parameter be used.*

Required Values

An absolute path or an environmental variable. This parameter is optional.

Additional Information

Existing environment variables may be referenced in this parameter by enclosing the variable name in a pair of % signs. For example:

```
%MY_CLASSPATH%
```

CLASSPATH Append From Environment Variable

Description

Specifies whether the path is appended for the CLASSPATH environmental variable to jar and zip files needed by the JVM.

Required Values

YES or NO. The configured default is YES.

Initial Heap Size

Description

Specifies the value for the initial heap size in bytes. If set to 0 (zero), the preferred value for the initial heap size of the JVM is used.

Required Values

An integer between 0 and 2147483647. This parameter is optional.

Maximum Heap Size

Description

Specifies the value of the maximum heap size in bytes. If set to 0 (zero), the preferred value for the maximum heap size of the JVM is used.

Required Values

An integer between 0 and 2147483647. This parameter is optional.

Maximum Stack Size for Native Threads

Description

Specifies the value of the maximum stack size in bytes for native threads. If set to 0 (zero), the default value is used.

Required Values

An integer between 0 and 2147483647. This parameter is optional.

Maximum Stack Size for JVM Threads

Description

Specifies the value of the maximum stack size in bytes for JVM threads. If set to 0 (zero), the preferred value for the maximum heap size of the JVM is used.

Required Values

An integer between 0 and 2147483647. This parameter is optional.

Disable JIT

Description

Specifies whether the Just-In-Time (JIT) compiler is disabled.

Required Values

YES or **NO**.

Note: This parameter is not supported for Java Release 1.

Remote Debugging port number

Description

Specifies the port number by which the e*Gate Java Debugger can connect with the JVM to allow remote debugging.

Required Values

An unused port number in the range 2000 through 65535. If not specified, the e*Gate Java Debugger is not able to connect to this e*Way.

Suspend option for debugging

Description

Allows you to specify that the e*Way should do no processing until an e*Gate Java Debugger has successfully connected to it.

Required Values

YES or **No**. **YES** suspends e*Way processing until a Debugger connects to it. **NO** enables e*Way processing immediately upon startup.

Auxiliary JVM Configuration File

Description

Specifies an auxiliary JVM configuration file for additional parameters.

Required Values

The location of the auxiliary JVM configuration file.

3.3 Configuring the Web Server Components

Each Web server requires different configuration. Consult your Web server documentation for more information.

3.3.1. Configuring Apache Web Server

Configuring the Web server to use the CGI e*Way components on Apache Web server

The Web server should run the client executable, **stccgi.exe**, when a request is received. It must also set the dynamic-load library path in order for **stc_msapi.dll**, **stc_msclient.dll**, and **stc_mscommon.dll** to be loaded by **stccgi.exe**.

- 1 Modify the Web server configuration file to include the dynamically loaded library path (LD_LIBRARY_PATH, SHLIB_PATH, LIBPATH, or PATH) which contains the path of the e*Gate API Kit JMS client dll files, **stc_msclient.dll**, **stc_mscommon.dll** and **stc_msapi.dll**.

For example, the Apache Web server on Solaris should appear as:

```
setenv LD_LIBRARY_PATH "/usr/egate/client/bin"
```

- 2 Copy the **stccgi.exe** and **mscgi.properties** to the CGI bin directory and modify **mscgi.properties** to configure the CGI executable.
- 3 Change the permission on **stccgi.exe**, **stc_msapi.dll**, **stc_msclient.dll** and **stc_mscommon.dll**, enabling them to be read and executed by the Web server.

Note: Consult the Web server documentation for more information.

- 4 Copy the test*.html file to the Web server's doc root.

For example, the Apache Service directory is:

```
Apache\htdocs.
```

- 5 Access the test*.html file from a Web browser, and send a file to the CGI Web Server e*Way server. If successful, the file you sent to the server is displayed. The URL used to access the stccgi.exe is:

```
http://hostname:port/cgi-bin/stccgi.exe
```

A sample HTML form used to access stccgi.exe appears below:

```
<HTML>

<FORM ACTION="cgi-bin/stccgi.exe" METHOD="POST"
ENCTYPE="multipart/form-data">
Multipart test
<P>
<TABLE>
  <TR>
    <TD><LABEL for="fname">First name: </LABEL>
    <TD> <INPUT type="text" name="firstname" id="fname">
  <TR>
    <TD><LABEL for="lname">Last name: </LABEL>
    <TD><INPUT type="text" name="lastname" id="lname">
  </TABLE>
  <LABEL for="email">email: </LABEL>
```

```
<INPUT type="text" name="email"><BR>
<INPUT type="radio" name="sex" value="Male"> Male<BR>
<INPUT type="radio" name="sex" value="Female"> Female<BR>
<LABEL for="filename">What files are you sending? </LABEL>
  <INPUT type="file" name="filename"><BR>
  <INPUT type="submit" value="Send"> <INPUT type="reset">
</P>
</FORM>

</HTML>
```

3.3.2. Configuring IIS Web Server

Configuring the Web server to use the CGI e*Way components on IIS Web server

The Web server should run the client executable, **stccgi.exe**, when a request is received. It must also set the dynamic-load library path in order for **stccgi.exe** to load **stc_msapi.dll**, **stc_mscommon.dll** and **stc_msclient.dll**.

- 1 Create the cgi-bin directory in the Inetpub directory.

If the default IIS server installation was used, the root directory is:

```
\inetpub
```


For example, create the following directory:

```
\inetpub\cgi-bin
```

Note: *The creation of this directory is not mandatory, but is recommended to assist with maintenance and to conform to common industry practices. The cgi-bin directory is used to store all cgi applications.*

- 2 Using the Internet Information Services Manager, go to Start\Settings\Control Panel\Administrative Tools\Internet Services Manager, or using Internet Information Services snap-in in Win 2K advanced server, create a virtual directory. To create a virtual directory, select Default Web Site in IIS manager, right click and choose action New\Virtual Directory. Alias: cgi-bin; Directory: C:\inetpub\cgi-bin, (Use the same directory as created in the preceding step) Access permissions: Read, Run Scripts and Execute.

Figure 6 IIS Internet Services Manager



- 3 Copy the **stccgi.exe**, **stc_msapi.dll**, **stc_msclient.dll** and **stc_mscommon.dll** to the CGI bin directory.
- 4 Create/copy a test.html file to:
 - C:\inetpub\wwwroot
 or the doc root that was configured for IIS server.

- 5 Modify **mscgi.properties** to configure the CGI executable. Change the permission on **stccgi.exe**, **stc_msapi.dll**, **stc_msclient.dll** and **stc_mscommon.dll**, enabling them to be read and executed by the Web server.

For IIS, ensure that for the directory created above (cgi-bin), the Execute Permissions setting is set to "Scripts and Executables". To modify this setting, go to Internet Service Manager, click on the Web site (for example, Default Web Site), right-click on Scripts and select Properties. In the Scripts Properties window, click on the Virtual Directory tab. Select "Scripts and Executables" on the Execute Permissions scroll menu. Select OK, then restart the Web server.

Note: Consult the Web server documentation for more information.

- 6 Access the test*.html file from a Web browser and send a file to the CGI Web Server e*Way server. If successful, the file you sent to the server is displayed. The URL used to access the stccgi.exe is:

```
http://hostname/cgi-bin/stccgi.exe
```

A sample HTML form used to access stccgi.exe appears as follows:

```
<HTML>
```

```
<FORM ACTION="/cgi-bin/stccgi.exe" METHOD="POST">
```

```
ENCTYPE="multipart/form-data">
Multipart test
<P>
<TABLE>
  <TR>
    <TD><LABEL for="fname">First name: </LABEL>
    <TD> <INPUT type="text" name="firstname" id ="fname">
  <TR>
    <TD><LABEL for="lname">Last name: </LABEL>
    <TD><INPUT type="text" name="lastname" id="lname">
</TABLE>
<LABEL for="email">email: </LABEL>
  <INPUT type="text" name="email"><BR>
<INPUT type="radio" name="sex" value="Male"> Male<BR>
<INPUT type="radio" name="sex" value="Female"> Female<BR>
<LABEL for="filename">What files are you sending? </LABEL>
  <INPUT type="file" name="filename"><BR>
<INPUT type="submit" value="Send"> <INPUT type="reset">
</P>
</FORM>

</HTML>
```


3.3.3. Configuring iPlanet Web Server

To configure the Web server to use the CGI e*Way Web server components on iPlanet Web server

The Web server should run the client executable, **stccgi.exe**, when a request is received. It must also set the dynamic-load library path in order for **stccgi.exe** to load **stc_msapi.dll**, **stc_mscommon.dll** and **stc_msclient.dll**.

- 1 Access the iPlanet Admin Web site. Select Server Manager and configure Programs \ CGI Directory as displayed in Figure 7:

Figure 7 iPlanet Server Manger



- Copy the `stccgi.exe`, `stc_msapi.dll`, `stc_msclient.dll` and `stc_mscommon.dll` to the following CGI bin directory:
 /NetScape/Server4/cgi-bin
- Modify `mscgi.properties` to configure the CGI executable. Change the permission on `stccgi.exe`, `stc_msapi.dll`, `stc_msclient.dll` and `stc_mscommon.dll`, enabling them to be read and executed by the Web server.

Note: Consult the Web server documentation for more information.

- Access the `test*.html` file from a Web browser and send a file to the CGI Web Server e*Way server. If successful, the file you sent to the server is displayed. The URL used to access the `stccgi.exe` is:

```
http://hostname/cgi-bin/stccgi.exe
```

A sample HTML form used to access `stccgi.exe` appears as follows:

```
<HTML>

<FORM ACTION="/cgi-bin/stccgi.exe" METHOD="POST"
ENCTYPE="multipart/form-data">
Multipart test
<P>
<TABLE>
  <TR>
    <TD><LABEL for="fname">First name: </LABEL>
    <TD> <INPUT type="text" name="firstname" id="fname">
  <TR>
    <TD><LABEL for="lname">Last name: </LABEL>
    <TD><INPUT type="text" name="lastname" id="lname">

```

```
</TABLE>
  <LABEL for="email">email: </LABEL>
    <INPUT type="text" name="email"><BR>
  <INPUT type="radio" name="sex" value="Male"> Male<BR>
  <INPUT type="radio" name="sex" value="Female"> Female<BR>
  <LABEL for="filename">What files are you sending? </LABEL>
    <INPUT type="file" name="filename"><BR>
  <INPUT type="submit" value="Send"> <INPUT type="reset">
</P>
</FORM>
</HTML>
```

3.3.4. Modifying the mscgi.properties File

The **mscgi.properties** file must be edited before the CGI e*Way is run. The file contains information pertaining to the JMS Connection, CGI Data, and Logging values.

The properties file is loaded by the SeeBeyond JMS CGI. Each property is a name/value pairing. The name uniquely identifies the property. The value is the content associated with that name. The name is separated from the value with the ':' character.

Important: DO NOT change names.

JMS Connection Section

Host

The name of the host on which the Message Service is running. The SeeBeyond JMS IQ Manager acts as the Message Service (server). If Host is not specified, then localhost is the default value.

```
Host:localhost
```

Port

The port at which the Message Service is listening for connections. If the port is not specified, then 7555 is the default value.

```
Port:24053
```

RequestReply

Selects the JMS delivery mode as Request/Reply or Publish/Subscribe. Specify **True** for Request/Reply mode; See **"Timeout"** to configure reply Timeout. Specify **False** for Publish or Send mode.

```
RequestReply:True
```

Timeout

Timeout for Request/Reply. This specifies the timeout in milliseconds to wait for the reply. This is used only for the Request/Reply mode. See **"RequestReply"**.

```
Timeout:60000
```

TopicRequest

Selects the JMS mode as Topic or Queue request. Specify **True** for Topic requests. See **“Topic”** to configure the JMS Topic. Specify **False** for Queue requests. See Queue to configure the JMS Queue. The default is Topic request.

```
TopicRequest:True
```

Topic

The JMS Topic that the CGI uses to send a message to the Message Service. There is no default value for this property. This must be specified for Topic requests. See **“TopicRequest”**.

For example, Topic:etRequestReplyTopic121. This is the same value as the ETD type name, which the participating host receives. Refer to the sample schema for more information.

```
Topic:etwebRequestETDTopic
```

Queue

The JMS Queue that CGI uses to send a message to the Message Service. There is no default value for this property. This must be specified for Queue requests. See **“TopicRequest”**. For example, Queue:etRequestReplyQueue.

```
Queue:etwebRequestETDTopic
```

ClientID

The Client ID to use for the JMS connection. For example, ClientID:SeeBeyondMSCGI.

```
ClientID:SeeBeyondMSCGI1
```

CGI Data Section

If the **webRequest ETD** is used, the **EnvInBody** value must be **False** and **EnvAsProps** value must be **True**. For all other combinations a custom ETD must be created. See [Figure 8 on page 30](#) for more information.

EnvInBody

Include the CGI Environments in the message body. If **True**, then each CGI environment is added before the CGI message body. Each environment is a name/value pair with '=' separating the name from the value. Each environment is separated by a new line. If **False**, then the CGI environments are not added to the message body. See **“EnvEnd”**.

EnvEnd

The text denoting the end of the Environment values. If EnvInBody is set to **True**, EnvStart is used to separate the message body from the environments. See **“EnvInBody”**. Do not change this value.

```
EnvEnd:<--End Environments-->
```

EnvsAsProps

IF **True**, Include the CGI Environment as JMS Properties. Each CGI environment is added to the JMS message as a JMS string property. If the webRequestETD is also used to receive the message the value of the JMS property is returned in the node

“environmentVariable”. When using a custom ETD, and not using webRequestETD, to receive the message, then call the readProperty method. For example:

```
getIn().readProperty(CONTENT_TYPE)
```

Figure 8 CGI Data - EnvInBody/EnvAsProps

EnvInBody	EnvAsProps	Application
True	True	Used with a Custom ETD. The JMS message is: all cgi env variables as name/value pair with name=value, followed by EnvEnd, followed by content body (if http post) or nothing (if http get). If the custom ETD does not read these JMS properties, unused additional data is sent.
False	True	webRequestETD can be used, or a custom ETD can be created for more options. The JMS message should appear as follows: <--End Environments--> followed by the content body (if http-post) or nothing (if http-get), followed by the tag <--End Environments--> regardless of what is defined in EnvEnd.
True	False	Used with a Custom ETD. The JMS message is the same as it is for True/True, except that it lacks all of the JMS properties. EnvEnd is used to separate the header from content body.
False	False	Used with a Custom ETD. The JMS message is: EndEnv followed by content body (if http post) or nothing (if http get).

ReadChunksize

When cgi does **read** from standard in, ReadChunksize specifies the chunk size, in bytes, of data to be read.

If you specify 1024 then cgi reads 1024 bytes of data once a time. If the content length is less than the chunk size, CGI just does read based on the content length. The default internal read chunk size is 409600 bytes. ChunkSize is an integer value, the maximum you can specify is 2147483647 bytes.

```
ReadChunksize:409600
```

WriteChunksize

When cgi does write to standard out, WriteChunksize specifies the chunk size in bytes, of the data to be written at one time. If you specify 1024 then cgi writes 1024 bytes of data once a time. The default internal write chunk size is 409600 bytes. ChunkSize is an integer value, the maximum you can specify is 2147483647 bytes.

```
WriteChunksize:409600
```

Log Section

LogFile

The log filename. Messages are logged into this file. See “Trace” to set the trace/log level.

```
LogFile:mscgi.log
```

Trace

The trace level to use for trace/debug. The following are valid values:

- 0 - Information
- 1 - Warning
- 2 - Error
- 3 - Fatal

```
Trace:0
```

3.3.5. Hex Dump vs. Text Dump

The CGI e*Way Web server component provides “dumps” (the contents of each message written to the log file), of every inbound (request) and outbound (reply) message that it handles, provided that the Trace level in the mscgi.properties file is set to “0”.

There are two types of dumps that can occur, a text dump and a hex dump. Text dumps are formatted into standard text. Hex dumps are formatted into lines of 16-bytes with two representations each, in its own section. The first section is the hex representation of 16-bytes, followed by the second, which contains the ASCII representation of the same 16-bytes. If any byte is non-printable, a dot is substituted. The type of dump which occurs, is determined by the content-type of the message.

If the inbound message to the CGI e*Way (the data read from the CGI stdin) is any content-type other than text/*, a hex dump occurs. If the content-type is text/*, a text dump occurs. The inbound hex dump does not include any environment variables from HTTP server, such as CONTENT_TYPE, CONTENT_LENGTH, PATH or HTTP_ACCEPT.

If the **Default Outgoing Message Type** parameter in the e*Way Connection configuration is set to publish “bytes” message, a hex dump occurs. If it is set to publish “text” messages, a text dump occurs.

Sample Hex Dump

```
MS-CGI (main.cxx:755) I:  2D -----
MS-CGI (main.cxx:755) I:  2D -----7d2
MS-CGI (main.cxx:755) I:  31 32 35 37 35 30 33 38 36 0D 0A 43 6F 6E 74 65 125750386..Conte
MS-CGI (main.cxx:755) I:  6E 74 2D 44 69 73 70 6F 73 69 74 69 6F 6E 3A 20 nt-Disposition:
MS-CGI (main.cxx:755) I:  66 6F 72 6D 2D 64 61 74 61 3B 20 6E 61 6D 65 3D form-data; name=
MS-CGI (main.cxx:755) I:  22 66 69 72 73 74 6E 61 6D 65 22 0D 0A 0D 0A 66 "firstname"....f
MS-CGI (main.cxx:755) I:  69 72 73 74 6E 61 6D 65 0D 0A 2D 2D 2D 2D 2D 2D irstname..-----
```

Sample Text Dump

If you submit http request with content type text/*, you get text dump.

```
MS-CGI (main.cxx:701) I:  SUCCESSFULLY Set CGI STDIN to BINARY MODE
MS-CGI (main.cxx:720) I:  Read accumulated data size [8192] and actual read size [8192]
MS-CGI (main.cxx:731) I:  Dump data chunk :
MS-CGI (main.cxx:732) I:
```

Text dump (by setting connection point to publish text message)

```
MS-CGI (Reply.cxx:167) I: Returning message of type TextMessage
MS-CGI (main.cxx:273) I:  ~!@#$$%^&*(_+`-={}|[]\:"';'<>?,./
0123456789abcdefghijklmnopqrstuvwxyzABCDEFGHIJKLMNOPQRSTUVWXYZ
```


Implementation

4.1 The Request/Reply Model

All the applications of the CGI Web Server e*Way are based upon the “Request/Reply” concept. At a high-level, this works as follows:

- 1 Request/Reply, where data is sent to the e*Gate system and a response is returned.
- 2 Send-only or Fire and Forget, where data is sent to e*Gate but no data is returned. (See Figure 9.)

Figure 9 The Request/Reply concept




4.1.1. Request/Reply and the CGI Web Server e*Way Participating Host Components

The CGI Web Server e*Way Participating Host component is a Multi-Mode e*Way that uses a proprietary IP-based protocol to multi-thread Event exchange between the e*Way and external systems or other e*Gate components.

Figure 10 illustrates how the e*Way receives data from an external application and returns processed data to the same application. (See Figure 10.)

Figure 10 Data flow



- 1 The user accesses one of the test*.html files from a Web browser, sending a file to the CGI Web Server e*Way server, using either HTTP Post or Get.
- 2 A JMSRequest is made, the JMSReplyTo property is assigned, and a TemporaryTopic subscriber is created.
- 3 The JMSRequest is passed to the JMS Server (also known as the SeeBeyond JMS IQ Manager), which then uses the etwebRequestETDTopic Event Type name to forward the text message to an e*Way Collaboration.
- 4 Collaborations within the e*Way perform any appropriate processing that may be required, and route the processed Events to other destinations (such as to an external system for additional data retrieval or processing and then back to the Web server as a Reply, using TemporaryTopic).
- 5 The Web server gets the content from TemporaryTopic, and replies to the Web client.

4.1.2. The Request/Reply Sample

The sample schema can be found in the e*Gate installation CD-ROM in the **samples/ewcgi/Java** directory.

e*Gate Request/Reply Sample Set up

Request Reply Sample

- 1 Install the CGI Web Server e*Way Server add on.
- 2 Import the sample schema. For e*Gate 4.5.1 or higher, go to the e*Gate Enterprise Manager's File menu and select "Import Definitions from File". Select Schema in the Import wizard, select **webETD_CGI.zip** for **Schema File Name**. **RequestReply.zip** is the file supplied in this sample directory.

Note: These instructions also appear in the "readme" file in the CGI Web Server e*Way samples directory (**samples/ewcgi/java**).

Once the client and server are set up, you can test the entire system using a Web browser:

- 1 Start the Control Broker. This also starts the JMS Server (SeeBeyond JMS IQ Manager).
- 2 Start the desired e*Way. In the sample, each e*Way demonstrates different functionality.
- 3 Use a browser to open the **test*.html** file.
- 4 Fill out and submit the form.
- 5 Confirm that the **stccgi.exe** returned the form data as expected. You can view the mscgi.log file, located in cgi-bin, to see the content sent out/received by stccgi.exe from the JMS Server.


Sample Functionality

Separate e*Ways handle various activities. There are four basic steps involved in a standard Request/Reply schema:

- 1 Define the content.
- 2 Populate the webReplyETD payload.
- 3 Call the send method in the webReplyETD.
- 4 Using the JMSReplyTo property, send the input to the webRequestETD.

Once successfully installed, the Enterprise Manager opens to the following:

Figure 11 webETD_CGI Enterprise Manager Components View



The sample is comprised of one e*Way:

- ewwebRequestETDReplyETD

ewwebRequestETDReplyETD

The ewwebRequestETDReplyETD e*Way receives a block of data, parses the input into webRequestETD, allows the creation of webReplyETD, then marshals the data into a block, and sends the block of data back.

crRequestReply_webRequestETDReplyETD

The Collaboration Rule associated with the ewwebRequestETDReplyETD e*Way performs the following:

- 1 Provides the HTTP content type for the reply message.
- 2 Gets the specified HTTP headers that CGI passes back to the Web server.
- 3 Demonstrates how to get the decoded inbound payload.
- 4 Demonstrates how to set outbound encoding. (Encoding is performed automatically and is not required.)
- 5 Shows charSet encoding/decoding activity. You perform a get of the decoded charSet payload from textStringPayload. If you require outbound encoding of the charSet, set the outbound charSet attributes.


- 6 Demonstrates how to get multiPart payload, and how to drill down on nested multiPart payload.
- 7 Demonstrates how to build an outbound multiPart payload.
- 8 Demonstrates how to get HTTP_GET URLEncoded name value pairs. The URLEncoded string is decoded into name value pairs.
- 9 Sends the HTTP-enabled data to the specified reply topic.

colRequestETDReplyETD

The Collaboration that ties the e*Way and the Collaboration Rule together is “colRequestETDReplyETD”. The Collaboration must have an Event Type and Source/Destination defined. For colRequestReply, the Collaboration subscribes to etWebRequestETD as a temporary topic. Keep in mind that stccgi.exe has been configured to publish etWebRequestETD topic. This is where the publication and subscription of the topic are seen. The temporary topic serves as a reply to the request, and is therefore transparent to the user. The exact temporary topic is stored in the input Event JMSReplyTo node.

The Collaborations subscribe and publish to the same external source/destination “cpBackstaryJMS” (the e*Way Connection).

Figure 12 colRequestETDReplyETD




4.1.3. Event Type Definitions

As discussed in [Request/Reply and the CGI Web Server e*Way Participating Host Components](#) on page 33, the CGI Web Server e*Way maintains the “JMSReplyTo” property. “JMSReplyTo” must be set to facilitate the reply data flow through the e*Gate system.

webRequestETD

The **webRequestETD** Event Type Definition (ETD) which can be used within a Request/Reply schema is shown below. The **webRequestETD** is designed to be “read only,” and the **webReplyETD** is designed to be “write only.”

Figure 13 The webRequestETD



Node Descriptions

contentType

The top level node “**contentType**” represents the CONTENT_TYPE meta variable. If the message can be defined as a discrete-type media, such as **text/***, **image/***, the content type shows up at the top level.

The following subnodes appear below it.

charset

If the `charset` is not supported, or is misspelled, the decoding can not take place. In that case, use `rawBytePayload`, or `decodedBytePayload`. The `charset` encoding table is available at:

<http://www.ingrid.org/java/i18n/encoding/table.html>

The value can be null if the message doesn't use the `charset` attribute.

contentTypeEncoding

Indicates whether the content is encoded (base64, binary, and so forth) the field is not case sensitive. It may be return a null string if not transfer encoded.

primaryType

Indicates the primary content type. For example, text in `text/xml`.

subType

Indicates the sub type of the content. For example, `xml` in `text/xml`.

boundary

If it is **multipart/*** data, this node carries the value of the boundary. If the message is nested multipart, this simply provides the top level boundary.

getContentTypeParameter

Provides a method to be called to get any other content type attributes, such as `ContentID`, may also return a null string, if the attribute is not defined.

requestMethod

Returns the HTTP method (for example, POST or GET).

environmentVariables

A top level node that contains an array of cgi variables received or passed to `stccgi` (for example `HTTP_ACCEPT`).

name

Return the name of the environment variable.

value

Returns the value of the environment variable.

urlNameValueQueryPair

A top level node that contains an array. Check the count of this array; if it returns a value equal to zero, the content is not a URL encoded value pair. If HTTP server received a get command, a URL encoded query string is received. The ETD decodes the string and populates the name value pair for use directly.

name

The name of the part. For example:

`firstname`

value

The value of the part. For example:

`myfirstname`

body

A top level node that contains the body of the content for discrete types, such as text/* or image/*.

The following subnodes appear below it.

rawBytePayload

Contains raw byte data.

decodedBytePayload

If the content indicates that it has been transfer encoded in the **contentType** header, the content-transfer-encoding attribute decodes the rawBytePayload. The result is the decoded byte array, while rawBytePayload still contains the original encoded byte data.

textStringPayload

If the content primary type indicates that it is text based, a string is created from rawBytePayload (or decodedBytePayload, if the content has been transfer encoded). The resulting text string is a Java internal representation of the original text string, in the designated charSet character encoding.

For example, a byte stream of data is received that is EUC_JP character encoded, the textStringPayload produces a Java internal string representation (Unicode) of that Japanese character stream. It is not in EUC_JP encoding, but in Java Unicode.

If the charSet is not recognized by the java decoder, (for example, you misspelled EUC_JP to ECU_JP) then you are not provided with a textStringPayload. You can access the data from rawBytePayload or decodedBytePayload.

If the original message contains a content transfer encoded text string, the rawBytePayload, decodedBytePayload, and textStringPayload all contain data.

If you specify the content type as application/xml, rather than text/xml, this media form is not recognized as a text type. textStringPayload is not populated, even though the content body is a text based byte array. In this case the content must be retrieved from rawBytePayload or decodedBytePayload (if content transfer encoded).

If the content type is not text/* and is not multipart/*, the payload must be retrieved via rawBytePayload or decodedBytePayload (if content transfer encoded).

For example, to use the Content-Type: text/plain;Content-Transfer-Encoding="Quoted-Printable" with the text "Now is the time for all folk to come to the aid of cgieway", the quoted-printable transfer encoding appears as below:

```
Now is the time=  
For all folk to come=  
To the aid of cgieway=
```

For more information, refer to RFC2045 at:

<http://www.ietf.org/rfc/rfc2045.txt>.

Per RFC2045:

```
Content-Type:text/plain; charset=EUC_JP  
Content-transfer-encoding: base64
```

In accordance with RFC2045, the body is a base64 US_ASCII encoding of data that was originally in EUC_JP. After unmarshalling via `webRequestETD`, the `textStringPayload` provides a Java string Unicode encoding of the Japanese content originally in EUC_JP.

multiPart

A top level node used in conjunction with `multipart/*` content type data. The following subnodes are available:

disposition

The content-disposition of each body part in the multipart array. Check for null values. For example, `multipart/form` data has top level content type populated as `multipart/form:boundary=_____`. Each part has disposition form data.

contentID

Contains the **ContentID** attributes. Check for null values.

contentMD5

Returns the value of the "content-MD5" header field. Returns null if this field is unavailable or absent. MD5 is a 128 bit digital finger print.

description

Returns the "content-Description" field.

filename

Returns the value if the content contains a filename, otherwise returns null.

contentType

Allows access to all `contentType` parameters. Similar to the top level `contentType` node, `contentType` indicates the break down of attributes for this body part. Check for null values.

mimeBodyPartRawPayload

Contains the raw byte data.

mimeBodyPartDecodedPayload

If the content indicates that it has been transfer encoded in the `contentType` header, `content-transfer-encoding` attribute decodes the `rawBytePayload`, returning a decoded byte array. In this case, the `mimeBodyPartRawPayload` still contains the encoded byte data.

mimeBodyPartTextStringPayload

If the content primary type indicates that it is text data, a string is created from the `mimeBodyPartRawPayload` (or the `mimeBodyPartDecodedPayload` if the content is transfer encoded). The resulting text string is a Java internal representation of the original text string, in the designated `charSet` character encoding.

For example, a byte stream of data is received that is EUC_JP character encoded, the `textStringPayload` produces a Java internal string representation (Unicode) of that Japanese character stream. It is not in EUC_JP encoding, but in Java Unicode.

If the original message contains a content transfer encoded text string, the `mimeBodyPartRawBytePayload`, `mimeBodyPartDecodedBytePayload`, and `mimeBodyPartTextStringPayload` all contain data.

If the content type is specified as `application/xml`, rather than `text/xml`, this media form is not recognized as a text type. `mimeBodyPartTextStringPayload` is not populated, even though the content body is a text based byte array. In this case the content must be retrieved from `mimeBodyPartRawBytePayload` or `mimeBodyPartDecodedBytePayload` (if content transfer encoded).

If the content type is not `text/*` and is not `multipart/*`, the payload must be retrieved via `mimeBodyPartRawBytePayload` or `mimeBodyPartDecodedBytePayload` (if content transfer encoded).

For example, to use the `Content-Type: text/plain;Content-Transfer-Encoding="Quoted-Printable"` with the text "Now is the time for all folk to come to the aid of cgieway", the quoted-printable transfer encoding appears as below:

```
Now is the time=  
For all folk to come=  
To the aid of cgieway=
```

For more information, refer to RFC2045, (page 16) at <http://www.ietf.org/rfc/rfc2045.txt>.

Per RFC2045:

```
Content-Type:text/plain; charset=EUC_JP  
Content-transfer-encoding: base64
```

In accordance with RFC2045, the body is a base64 US_ASCII encoding of data that was originally, in EUC_JP. After unmarshalling via `webRequestETD`, the `textStringPayload` provides a Java string Unicode encoding of the Japanese content originally in EUC_JP.

mimeBodyPart

Returns an object of `javax.Mail.Internet.MimeBodyPart`. This value can be accessed via multipart nesting. This provides the means to access a raw object handle.

nestedMultiPart

If the multiPart contains another multipart, as an associated body part, this node allows for drilling down to the nested multiPart. If it is not nested, it returns null. The `mimeBodyPartRawPayload` and `decodedPayload` are maintained at the same time.

isMimeBodyPart

Queries whether the body part is of a mime type.

isMimeType

Queries whether the body part is of a certain mime type.

JMSReplyTo

Gets the **JMSReplyTo** property.

countEnvironmentVariable

Returns an integer, indicating the number of environment variables.

countMultiparts

Returns an integer, indicating the number of body parts.

isMultipart

Returns true or false, indicating whether multipart or not.

isUrlencoded

Returns true or false, indicating whether the data is URL encoded.

isSingleBody

Returns true or false, indicating whether the data consists of a single body part.


countURLNameValueQueryPairs

Returns an integer, indicating the number of name/value pairs.

webReplyETD

The **webReplyETD** Event Type Definition (ETD) is used within a Request/Reply schema. The **webReplyETD** mirrors the **webRequestETD**. The **webReplyETD** is “write” only, while the **webRequestETD** is “read” only. There are functions available to allow you to read the node value, but the node value must be set before reading.

Figure 14 The webReplyETD



Node Description

contentType

The **CONTENT_TYPE** header that is returned to the HTTP client. This **contentType** is prepended to the body with two carriage return line feeds (CRLFs).

The following subnodes appear below it.

charSet

Setting this value brings about a byte array of text data as the output. The body node's **textStringPayload** must also be set.

contentTransferEncoding

Setting this value defines the content as encoded (such as base64). If the data is multipart, do not set transfer encoding at the top level.

primaryType

Sets the primary content type. For example, text in text/xml.

subType

Sets the sub type of the content. For example, xml in text/xml.

boundary

This value is only set if the user does not want to use the system defined boundary. Do not set the boundary if the data is not multipart data.

setContentParameter

Sets a name/value pair in **contentType**.

getContentParameter

Gets a name/value pair from **contentType**.

addHeader

A method that allows the user to add other http/cgi response headers, taking a name/value pair as the parameters. It is not necessary to add **content_type** headers here since that is already accomplished by the setting the **contentType** node. The ETD bundles the **contentType** headers behind the scenes.

getHeader

A method that allows the user to retrieve the header. It takes a name/delim pair as the parameters.

setHeader

A method that allows the user to set the header value. It takes a name/value pair as the parameters.

body

A top level node. If the data is of the discrete type, such as text/* or image/*, the body of content appears here. Set **rawBytePayload** or **textStringPayload** (one, not both).

The following subnodes appear under **body**:

rawBytePayload

If the data is not text based, the raw byte data is contained here.

textStringPayload

Set this payload for text string based data. If this value is set, the content type is not verified. The text string can be any language, as specified by :

<http://www.ingrid.org/java/i18n/encoding/table.html>

Specify the output charSet, if the string contains any non-default text, such as EUC_JP, SJIS, GB2312, ISO-8859-1. The desired output character should be specified, even when a conversion is not performed. For example, if the textStringPayload contains java Unicode string EUC_JP, specify charSet=EUC_JP. The Unicode output results in a byte array that contains EUC_JP characters. If you set charSet=SJIS, the output results in Java Unicode encoding of the original EUC_JP string to a byte array that contains an SJIS character set.

multiPart

This is an array of body part. The ETD allocates a new body part the first time the body part attribute is accessed. Set each body part payload. If the boundary is set in the contentType node, that boundary value is used. If only header is set and not the payload, a marshalling exception occurs.

The following subnodes appear below:

disposition

Sets the disposition.

contentID

Sets the contentID.

contentMD5

Sets the MD5 signature.

description

Sets the description.

filename

Set the filename.

contentType

Allows the user to set the values of the following subnodes:

charSet

Setting this value produces a byte array of text data as output. The body node's **textStringPayload** must also be set.

contentTransferEncoding

Setting this value, cause a byte array of text data to result as the output. You must also then set the body node's **textStringPayload**.

primaryType

Sets the primary content type. For example, text in text/xml.

subType

Set the sub type of the content. For example, xml in text/xml.

boundary

This value is only set if you do not want to use the system defined boundary. Do not set if the data is not multipart.

setContentParameter

Sets a name/value pair in contentType.

getContentParameter

Gets a name/value pair from contentType.

mimeBodyPartRawPayload

Sets the body part payload to "raw".

mimeBodyPartDecodedPayload

Sets the body part payload to "decoded".

send

Sends the reply to the **JMSReply** property, taking the **replyTo** parameter string.

send

Sends the reply to the **JMSReply** property.

JMSReplyTo

Sets the **JMSReplyTo** property.

4.1.4. Collaboration Rules and the CGI Web Server Header

The Collaboration Rule provided in the sample (shown in Figure 15) demonstrates a number of possible behaviors.

- 1 Provide the HTTP content type for the reply/outbound message:

```
getout().getContentType().setPrimaryType( "text" )
getout().getContentType().setSubType( "plain" )
```

- 2 Get request/inbound CGI meta variables:

```
getin().getEnvironmentVariables(i).getName()
getin().getEnvironmentVariables(i).getValue()
```

- 3 Add another reply/outbound HTTP header:

```
getout().addHeader(getin().getEnvironmentVariables(i).getName(),ge
tin().getEnvironmentVariables(i).getValue())
```

- 4 Test/Get decoded inbound payload:

Multipart test:

```
getin().getMultiParts(j).getContentType().getContentTransferEncodi
ng()==null
```

Single body test:

```
getin().getContentType().getContentTransferEncoding()==null
```

Multipart get decoded payload:

```
byte[] temppayload=getin().getMultiParts(outmlptindex).getMimeBodyP
artDecodedPayload()
```

Single body decoded payload:

```
byte[] bytesinglebody=getin().getBody().getTransferCodePayload()
```

If it is text message, it is always decoded for you with:

```
String strsinglebody=getin().getBody().getTextStringPayload()
```

- 5 Set charSet or content transfer encoding for reply/outbound and set the proper payload (the encoding is performed automatically):

```
getout().getContentType().setCharset("SJIS")
getout().getMultiParts(outmlptindex).getContentType().setContentTransferEncoding("base64")
getout().getMultiParts(outmlptindex).setMimebodyPartTextStringPayload(getin().getMultiParts(j).getMimebodyPartTextStringPayload())
getout().getMultiParts(outmlptindex).setMimebodyPartRawPayload(temppayload)
```

- 6 Get URL encoded name/value pair:

```
getin().isUrlencoded()
strbuf4.append(" url name:
"+getin().getURLNameValueQueryPairs(k).getName()+" value:
"+getin().getURLNameValueQueryPairs(k).getValue())
```


- 7 Send the HTTP-enabled data to the reply topic:

Manual publish:

```
getout().send(getout().getJMSReplyTo())
```


crRequestReply_webRequestETDReplyETD

Figure 15 Copying the Request/Reply field



A portion of the Business Rules that were implemented for crRequestReply_webRequestETDReplyETD Collaboration Rules sample, appear below:

Figure 16 Business Rules



The code itself can be viewed from the GUI. From the **View** Menu, select **View Java Code**. The code appears as follows:

```
import com.stc.common.collabService.*;
import com.stc.jcsre.*;
import com.stc.eways.util.*;
import java.io.*;
import java.sql.*;
import java.util.*;
import com.stc.eways.webETD.*;

class crRequestReply_webRequestETDReplyETDBase extends JCollaboration
{
    public crRequestReply_webRequestETDReplyETDBase()
    {
        super();
    }

    com.stc.eways.webETD.webRequestETD in = null;

    public com.stc.eways.webETD.webRequestETD getin()
    {
        return this.in;
    }

    com.stc.eways.webETD.webReplyETD out = null;

    public com.stc.eways.webETD.webReplyETD getout()
    {
        return this.out;
    }

    public void resetData() throws CollabConnException, CollabDataException
    {
        this.in = (com.stc.eways.webETD.webRequestETD) this.reset((ETD)this.getin());
        this.out = (com.stc.eways.webETD.webReplyETD) this.reset((ETD)this.getout());
    }

    public void createInstances() throws CollabConnException
    {

```

```

        this.in = (com.stc.eways.webETD.webRequestETD)
this.newInstance("com.stc.eways.webETD.webRequestETD", "in", ETD.IN_MODE);
        this.out = (com.stc.eways.webETD.webReplyETD)
this.newInstance("com.stc.eways.webETD.webReplyETD", "out", ETD.OUT_MODE);
    }
}

public class crRequestReply_webRequestETDReplyETD extends
crRequestReply_webRequestETDReplyETDBase implements JCollaboratorExt
{
    public crRequestReply_webRequestETDReplyETD()
    {
        super();
    }

    public boolean executeBusinessRules() throws Exception
    {
        boolean retBoolean = true;
        int EnvVarCnt = getin().countEnvironmentVariables();
        System.err.println("boundary:"+getin().getContentType().getMultipartBoundary());
        for( int i = 0;i < EnvVarCnt;i++)
        {
            getout().addHeader(getin().getEnvironmentVariables(i).getName(),getin().getEnvironmentVariables(i)
            .getValue());
            if (getin().isMultipart())
            {
                getout().getContentType().setPrimaryType( "text" );
                getout().getContentType().setSubType("plain");
                //getout().getContentType().setMultipartBoundary("xi-li-hu-tu-yi-xian-tian-kai-zi-bian-
                zi-zao-boundary");
                int partscount = getin().countMultiParts();
                int outmlptindex = 0;
                for( int j = 0;j < partscount;j++)
                {
                    if (getin().getMultiParts(j).getDisposition() != null)
                    {
                        getout().getMultiParts(outmlptindex).setDisposition(getin().getMultiParts(j).getDisposition());
                    }
                    else
                    {
                        if (getin().getMultiParts(j).getDescription() != null)
                        {
                            getout().getMultiParts(outmlptindex).setDescription(
                            getin().getMultiParts(j).getDescription() );
                        }
                        else
                        {
                            if (getin().getMultiParts(j).getContentTypeString().indexOf("text") >= 0)
                            {
                                getout().getMultiParts(outmlptindex).getContentType().setPrimaryType(getin().getMultiParts(j).getC
                                ontentType().getPrimaryType() );
                                getout().getMultiParts(outmlptindex).getContentType().setSubType(
                                getin().getMultiParts(j).getContentType().getSubType() );
                                if (getin().getMultiParts(j).getContentType().getContentTransferEncoding() ==
                                null)
                                {
                                    getout().getMultiParts(outmlptindex).getContentType().setContentTransferEncoding("base64");
                                }
                                else
                                {
                                    if (getin().getMultiParts(j).getContentType().getCharSet() != null &&
                                    getin().getMultiParts(j).getContentType().getCharSet().compareToIgnoreCase("EUC_JP") == 0)
                                    {
                                        getout().getMultiParts(outmlptindex).getContentType().setCharSet("SJIS");
                                    }
                                    else
                                    {
                                        if (getin().getMultiParts(j).getContentType().getCharSet() != null)
                                        {
                                            getout().getMultiParts(outmlptindex).getContentType().setCharSet(
                                            getin().getMultiParts(j).getContentType().getCharSet() );
                                        }
                                        else
                                        {
                                            getout().getMultiParts(outmlptindex).setDisposition(
                                            getin().getMultiParts(j).getDisposition() );
                                            getout().getMultiParts(outmlptindex).setDescription("add a sample description in
                                            collab");
                                        }
                                    }
                                }
                            }
                        }
                    }
                }
            }
        }
    }
}

```

```

        getout().getMultiParts(outmlptindex).setFileName(
getin().getMultiParts(j).getFileName() );

getout().getMultiParts(outmlptindex).setMimeBodyPartTextStringPayload(getin().getMultiParts(j).get
MimeBodyPartTextStringPayload());
    outmlptindex++;
    }
    else
    {
        if (getin().getMultiParts(j).countNestedMultiPart() == 0)
        {
            if (getin().getMultiParts(j).getMimeBodyPartDecodedPayload() != null)
            {
                byte[] temppayload =
getin().getMultiParts(outmlptindex).getMimeBodyPartDecodedPayload();
                getout().getMultiParts(outmlptindex).setMimeBodyPartRawPayload(temppayload);
                getout().getMultiParts(outmlptindex).setDisposition(
getin().getMultiParts(j).getDisposition() );
                getout().getMultiParts(outmlptindex).setDescription(
getin().getMultiParts(j).getDescription() );
                getout().getMultiParts(outmlptindex).setFileName(
getin().getMultiParts(j).getFileName() );
                getout().getMultiParts(outmlptindex).getContentType().setPrimaryType(
getin().getMultiParts(j).getContentType().getPrimaryType());
                getout().getMultiParts(outmlptindex).getContentType().setSubType(
getin().getMultiParts(j).getContentType().getSubType() );
            }
            else
            {
                byte[] temppayload = getin().getMultiParts(j).getMimeBodyPartRawPayload();
                getout().getMultiParts(outmlptindex).setMimeBodyPartRawPayload(temppayload);
                getout().getMultiParts(outmlptindex).setDisposition(
getin().getMultiParts(j).getDisposition() );
                getout().getMultiParts(outmlptindex).setDescription(
getin().getMultiParts(j).getDescription() );
                getout().getMultiParts(outmlptindex).setFileName(
getin().getMultiParts(j).getFileName() );
                getout().getMultiParts(outmlptindex).getContentType().setPrimaryType(
getin().getMultiParts(j).getContentType().getPrimaryType());
                getout().getMultiParts(outmlptindex).getContentType().setSubType(
getin().getMultiParts(j).getContentType().getSubType() );
            }
        }
        outmlptindex++;
    }
    else
    {
        int cntnestedpart = getin().getMultiParts(j).countNestedMultiPart();
        for( int l = 0;l < cntnestedpart;l++)
        {
            if
(getin().getMultiParts(j).getNestedMultiPart(l).getMimeBodyPartDecodedPayload() != null)
            {
                byte[] temppayload =
getin().getMultiParts(j).getNestedMultiPart(l).getMimeBodyPartDecodedPayload();
                getout().getMultiParts(outmlptindex).setMimeBodyPartRawPayload(temppayload);
                getout().getMultiParts(outmlptindex).setDisposition(
getin().getMultiParts(j).getNestedMultiPart(l).getDisposition() );
                getout().getMultiParts(outmlptindex).setDescription(
getin().getMultiParts(j).getNestedMultiPart(l).getDescription() );
                getout().getMultiParts(outmlptindex).setFileName(
getin().getMultiParts(j).getNestedMultiPart(l).getFileName() );
                getout().getMultiParts(outmlptindex).getContentType().setPrimaryType(
getin().getMultiParts(j).getNestedMultiPart(l).getContentType().getPrimaryType());
                getout().getMultiParts(outmlptindex).getContentType().setSubType(
getin().getMultiParts(j).getNestedMultiPart(l).getContentType().getSubType() );
            }
            else
            {
                byte[] temppayload =
getin().getMultiParts(j).getNestedMultiPart(l).getMimeBodyPartRawPayload();
                getout().getMultiParts(outmlptindex).setMimeBodyPartRawPayload(temppayload);
                getout().getMultiParts(outmlptindex).setDisposition(
getin().getMultiParts(j).getNestedMultiPart(l).getDisposition() );
                getout().getMultiParts(outmlptindex).setDescription(
getin().getMultiParts(j).getNestedMultiPart(l).getDescription() );
                getout().getMultiParts(outmlptindex).setFileName(
getin().getMultiParts(j).getNestedMultiPart(l).getFileName() );
                getout().getMultiParts(outmlptindex).getContentType().setPrimaryType(
getin().getMultiParts(j).getNestedMultiPart(l).getContentType().getPrimaryType());
                getout().getMultiParts(outmlptindex).getContentType().setSubType(
getin().getMultiParts(j).getNestedMultiPart(l).getContentType().getSubType() );
            }
        }
        outmlptindex++;
    }
    }
}
}
}
else
{

```

```

        System.err.println("Not Multiupart");
    }
    String strsinglebody;
    byte[] bytesinglebody;
    if (getin().isSingleBody())
    {
        getout().getContentType().setPrimaryType(getin().getContentType().getPrimaryType());
        getout().getContentType().setSubType(getin().getContentType().getSubType());
        if (getin().getBody().getTextStringPayload() != null)
        {
            strsinglebody=getin().getBody().getTextStringPayload();
            getout().getBody().setTextStringPayload(strsinglebody);
            if (getin().getContentType().getCharSet() != null &&
                getin().getContentType().getCharSet().compareToIgnoreCase("EUC_JP")==0)
            {
                getout().getContentType().setCharSet("SJIS");
            }
            else
            {
                if (getin().getContentType().getCharSet() != null)
                {
                    getout().getContentType().setCharSet(getin().getContentType().getCharSet());
                }
                else
                {
                }
            }
        }
        else
        {
            if (getin().getBody().getTransferCodePayload() != null)
            {
                bytesinglebody = getin().getBody().getTransferCodePayload();
                getout().getBody().setRawPayload(bytesinglebody);
            }
            else
            {
                bytesinglebody = getin().getBody().getRawPayload();
                getout().getBody().setRawPayload(bytesinglebody);
            }
            System.err.println("Single body does not have text payload");
        }
    }
    else
    {
        System.err.println("is not single body type");
    }
    StringBuffer strbuf4 = new StringBuffer();
    if (getin().isUrlencoded())
    {
        for( int k = 0;k < getin().countURLNameValueQueryPairs();k++)
        {
            strbuf4.append(" url name: "+getin().getURLNameValueQueryPairs(k).getName()+" value:
"+getin().getURLNameValueQueryPairs(k).getValue());
        }
        getout().getContentType().setPrimaryType("text");
        getout().getContentType().setSubType("plain");
        getout().getBody().setTextStringPayload(strbuf4.toString());
    }
    else
    {
        System.err.println("not url encoded request");
    }
    getout().setJMSReplyTo(getin().getJMSReplyTo());
    getout().send(getout().getJMSReplyTo());
    ;
    return retBoolean;
}

public void userInitialize()
{
}

public void userTerminate()
{
}
}

```

Once the sample functions to your satisfaction, you can modify the schema to add functionality or create a new schema.

4.1.5. Test HTML Files

There are two test HTML files provided with the sample:

- testmultptfrm.html
- testurlencoded.html

testmultptfrm.html

The testmultptfrm.html file, for multi-part form data exchange, appears below:

Figure 17 testmultptfrm.html

The HTML code follows:

```
<HTML>


<FORM ACTION="cgi-bin/stccgi.exe" METHOD="POST"
ENCTYPE="multipart/form-data">
Multipart test
<P>
<TABLE>
  <TR>
    <TD><LABEL for="fname">First name: </LABEL>
    <TD> <INPUT type="text" name="firstname" id ="fname">
  <TR>
    <TD><LABEL for="lname">Last name: </LABEL>
    <TD><INPUT type="text" name="lastname" id="lname">
</TABLE>
<LABEL for="email">email: </LABEL>
  <INPUT type="text" name="email"><BR>
  <INPUT type="radio" name="sex" value="Male"> Male<BR>
  <INPUT type="radio" name="sex" value="Female"> Female<BR>
  <LABEL for="filename">What files are you sending? </LABEL>
  <INPUT type="file" name="filename"><BR>
  <INPUT type="submit" value="Send"> <INPUT type="reset">
</P>
</FORM>

</HTML>
```

testurlencoded.html

The testurlencoded.html file is provided for name/value pair form data exchange and appears below:

Figure 18 testurlencoded.html



Hello!

First Name:

LastName Name:

EMail:

Male

Female

What files are you sending?

The HTML code appears as follows:

```
<FORM ACTION="cgi-bin/stccgi.exe" METHOD=POST>
Hello!
<P>
First Name:
<INPUT NAME=fname><BR>
<P>
LastName Name:
<INPUT NAME=lname><BR>
<P>
EMail:
<INPUT NAME=email><BR>
<p>
<INPUT type="radio" name="sex" value="Male"> Male<BR>
<p>
<INPUT type="radio" name="sex" value="Female"> Female<BR>
<P>
<LABEL for="filename">What files are you sending? </LABEL>
      <INPUT type="file" name="filename"><BR>
<P>
<INPUT TYPE=submit>
</FORM>
```

4.1.6. Message Routing to Multiple Collaborations

Only one type of topic can be published to each cgi-bin directory. If publishing many topics at the same time is a requirement, multiple cgi-bin directories can be set up. For example, cgi-bin, cgi-bin2, and so on. In each cgi-bin directory, there must be a copy of stccgi.exe, stc_msapi.dll, stc_msclient.dll, stc_mscommon.dll, and mscgi.properties. (For more information see [“Configuring the Web Server Components” on page 23.](#)) Modify the mscgi.properties file to point to the correct host and topic/queue to be published.

As an example, if the user wants to publish two topics, Topic:etwebRequestETDTopic and Topic:webRequest, the user modifies the mscgi.properties file, located in cgi-bin, to specify Topic:etwebRequestETDtopic. Topic:webRequest is specified in the mscgi.properties file, located in cgi-bin2. Both cgi-bin and cgi-bin2 directories must contain the same version of the above mentioned files. The user can then create two Collaboration Rules to subscribe to etwebRequestETDTopic and webRequest.

To submit Topic:etwebRequestETDTopic via an HTTP client, the URL format used is:

```
hostname:port\cgi-bin\stccgi.exe
```

To submit Topic:webRequest via an HTTP client, the URL used is:

```
hostname:port\cgi-bin2\stccgi.exe
```


To achieve this result, each Web server must be configured to allow multiple CGI directories.

For Apache, in httpd.conf insert lines equivalent to the following:

```
ScriptAlias /cgi-bin/ "C:/Program Files/Apache Group/Apache/cgi-bin/"
ScriptAlias /cgi-bin2/ "C:/Program Files/Apache Group/Apache/cgi-
bin2/"
```

For IIS, create two virtual directories for cgi-bin and cgi-bin2.

Figure 19 Dual IIS Virtual Directories



For iPlanet, configure the server to allow two CGI directories, cgi-bin and cgi-bin2.

Figure 20 iPlanet dual CGI directories

Current CGI directories		
Edit	Remove	Prefix: /cgi-bin2 CGI Directory: C:/Netscape/Server4/cgi-bin2
Edit	Remove	Prefix: /cgi-bin CGI Directory: C:/Netscape/Server4/cgi-bin

Methods

5.1 CGI Java e*Way Methods

The Collaboration Editor allows you to call methods by dragging and dropping the node into the Rules dialog box. The node name maybe different from the Java method name. The conversion takes place in the .xsc file. To view the .xsc file, use the ETD Editor.

For example, if the node name is “encoding”, the associated javaName is “Encoding”. If you want to “get” the node value, the Java method called is getEncoding. If you want to “set” the node value, the Java method called is setEncoding.

The CGI Java e*Way components support the following classes:

5.1.1. Class Hierarchy

```
class java.lang.Object
  class com.stc.eways.webETD.Body
  class com.stc.eways.webETD.NameValue
  class com.stc.eways.webETD.OneMimeBodyPart
  class com.stc.eways.webETD.OneMimeBodyPart.NestedMultiPart
  class com.stc.jcsre.SimpleETDImpl (implements com.stc.jcsre.ETD)
    class com.stc.jcsre.MsgETDImpl
      class com.stc.eways.webETD.webReplyETD (implements
        com.stc.jcsre.ETD)
      class com.stc.eways.webETD.webRequestETD (implements
        com.stc.jcsre.ETD)
    class com.stc.eways.webETD.webETDContentType
    class com.stc.eways.webETD.webETDInternetHeaders
    class com.stc.eways.webETD.webReplyETD.ReplyMultiParts
    class com.stc.eways.webETD.webRequestETD.EnvironmentVariables
    class com.stc.eways.webETD.webRequestETD.MultiParts
    class com.stc.eways.webETD.webRequestETD.URLNameValueQueryPairs
```

5.2 Class Body

```
com.stc.eways.webETD
  java.lang.Object
  com.stc.eways.webETD.Body
  public class Body
  extends java.lang.Object
```

The Body Class methods are described in detail on the following pages:

[Body](#) on page 56

[getRawPayload](#) on page 56

[setRawPayload](#) on page 56

[getTransferCodePayload](#) on page 57

[setTransferCodePayload](#) on page 57

[getStringPayload](#) on page 58

[setTextStringPayload](#) on page 58

[marshal](#) on page 58

[unmarshal](#) on page 59

Body

Description

Constructor.

Syntax

```
public Body()
```

getRawPayload

Description

Gets the raw payload byte array

Syntax

```
public byte[] getRawPayload()
```

Parameters

None.

Returns

byte array

Returns a byte array of the raw payload.

Throws

None.

setRawPayload

Description

Sets the raw payload to the byte array

Syntax

```
public void setRawPayload(byte[] inrawpayload)
```

Parameters

Name	Type	Description
inrawpayload	byte[]	The raw payload to be set.

Returns

None.

Throws

java.io.IOException

getTransferCodePayload

Description

Returns the decoded byte array (Request) or encoded byte array (Reply).

Syntax

```
public byte[] getTransferCodePayload()
```

Parameters

None.

Returns

byte array

Returns the decoded or encoded byte array.

Throws

None.

setTransferCodePayload

Description

Sets the encoded payload to the byte array.

Syntax

```
public void setTrasferCodePayload(byte[] inpayload)
```

Parameters

Name	Type	Description
inpayload	byte[]	The payload to be set.

Returns

None.

Throws

java.io.IOException

getTextStringPayload

Description

Gets the charSet decoded string payload.

Syntax

```
public java.lang.String getTextStringPayload()
```

Parameters

None.

Returns

java.lang.String

Returns the decoded string payload.

Throws

None.

setTextStringPayload

Description

Sets the charSet encoded string payload.

Syntax

```
public void setTextStringPayload(java.lang.String inpayload)
```

Parameters

Name	Type	Description
inpayload	java.lang.String	The payload to be set.

Returns

None.

Throws

None.

marshal

Description

The out bound Collaboration controller calls this marshal method, you only need to either set rawpayload or text string payload.

Syntax

```
public byte[] marshal(java.lang.String encodingstyle,
    java.lang.String charset, boolean isText)
```

Parameters

Name	Type	Description
encodingstyle	java.lang.String	The encoding style.
charset	java.lang.String	The charset.
isText	boolean	true indicates the payload is set to text.

Returns

byte array

Returns a byte array of flattened data.

Throws

com.stc.jcsre.MarshalException

unmarshal

Description

Takes a byte array and parses it into raw payload, decoded payload or string payload based on the content type.

Syntax

```
public void unmarshal(byte[] bytearraybodyin,webETDContentType
    contenttype)
```

Parameters

Name	Type	Description
bytearraybodyin	byte[]	An inbound byte array.
contenttype	webETDContentType	The content type to which to parse the data.

Returns

None.

Throws

com.stc.jcsre.UnmarshalException

5.3 Class NameValue

```
java.lang.Object
    com.stc.eways.webETD.NameValue
```

```
public class NameValue  
    extends java.lang.Object
```

The NameValue Class methods are described in detail on the following pages:

[NameValue](#) on page 60

[setIsURLencoded](#) on page 61

[getName](#) on page 60

[marshal](#) on page 61

[getValue](#) on page 60

[unmarshal](#) on page 62

NameValue

Description

Constructor

Syntax

```
public NameValue()  
public NameValue(java.lang.String nmin, byte[] valin)
```

Parameters

Name	Type	Description
nmin	java.lang.String	The name.
valin	byte[]	A byte array of value.

getName

Description

Gets the name of the variable.

Syntax

```
public java.lang.String getName()
```

Parameters

None.

Returns

java.lang.String
Returns the name of the variable.

Throws

None.

getValue

Description

Gets the value of this pair.

Syntax

```
public byte[] getValue()
```

Parameters

None.

Returns**byte array**

Returns value as a byte array.

Throws

None.

setIsURLencoded**Description**

Marks this pair as URL encoded.

Syntax

```
public void setIsURLencoded(boolean isEncoded)
```

Parameters

Name	Type	Description
isEncoded	boolean	true indicates that the part is URL encoded.

Returns

None.

Throws

None.

marshal**Description**

Marshal serializes this object into a byte array.

Syntax

```
public byte[] marshal()
```

Parameters

None.

Returns**byte array**

Returns the corresponding deserialized NameValue object.

Throws

`com.stc.jcsre.MarshalException`

unmarshal

Description

Unmarshal deserializes the byte array passed into this object.

Syntax

```
public void unmarshal(byte[] inputEvent)
```

Parameters

Name	Type	Description
inputEvent	byte[]	A byte array deserialized into a NameValue object.

Returns

None.

Throws

`com.stc.jcsre.UnmarshalException`

5.4 Class OneMimeBodyPart

```
com.stc.eways.webETD
java.lang.Object
    com.stc.eways.webETD.OneMimeBodyPart
public class OneMimeBodyPart
    extends java.lang.Object
```

The OneMimeBodyPart Class methods are described in detail on the following pages:

[OneMimeBodyPart](#) on page 63

[getMimeBodyPart](#) on page 63

[getMimeBodyPartRawPayload](#) on page 63

[setMimeBodyPartRawPayload](#) on page 64

[getMimeBodyPartDecodedPayload](#) on page 64

[getMimeBodyPartTextStringPayload](#) on page 65

[setMimeBodyPartTextStringPayload](#) on page 65

[isMimeBodyPart](#) on page 65

[isMimeType](#) on page 66

[getDisposition](#) on page 66

[getContentTypeString](#) on page 68

[setContentMD5](#) on page 68

[getContentMD5](#) on page 69

[getDescription](#) on page 69

[setDescription](#) on page 70

[getEncoding](#) on page 70

[getFileName](#) on page 70

[setFileName](#) on page 71

[getContentType](#) on page 71

[countNestedMultiPart](#) on page 72

[setDisposition](#) on page 67

[setContentID](#) on page 67

[getContentID](#) on page 68

[getNestedMultiPart](#) on page 72

[marshal](#) on page 72

[unmarshal](#) on page 73

OneMimeBodyPart

Description

Constructor.

Syntax

```
public OneMimeBodyPart()
```

getMimeBodyPart

Description

Returns a javax.mail.internet.MimeBodyPart object.

Syntax

```
public com.stc.eways.webETD.MimeBodyPart getMimeBodyPart()
```

Parameters

None.

Returns

com.stc.eways.webETD.MimeBodyPart

Returns a javax.mail.internet.MimeBodyPart object.

Throws

None.

getMimeBodyPartRawPayload

Description

Returns the raw payload byte array.

Syntax

```
public byte[] getMimeBodyPartRawPayload()
```

Parameters

None.

Return

byte[]

Returns a byte array of the raw payload.

Throws

javax.mail.MessagingException
java.io.IOException

setMimeBodyPartRawPayload**Description**

Sets the raw payload.

Syntax

```
public void setMimeBodyPartRawPayload(byte[] inbytearray)
```

Parameters

Name	Type	Description
inbytearray	byte[]	A byte array of the raw payload.

Return

None.

Throws

javax.mail.MessagingException
java.io.IOException

getMimeBodyPartDecodedPayload**Description**

Returns the decoded payload byte array.

Syntax

```
public byte[] getMimeBodyPartDecodedPayload()
```

Parameters

None.

Return

byte array
Returns a byte array of the decoded payload.

Throws

javax.mail.MessagingException

java.io.IOException

getMimeBodyPartTextStringPayload

Description

Returns the string payload.

Syntax

```
public java.lang.String getMimeBodyPartTextStringPayload()
```

Parameters

None.

Return

java.lang.String

Returns the string payload.

Throws

javax.mail.MessagingException

java.io.IOException

setMimeBodyPartTextStringPayload

Description

Sets the string payload.

Syntax

```
public void setMimeBodyPartTextStringPayload(java.lang.String instr)
```

Parameters

Name	Type	Description
instr	java.lang.String	The inbound string to set.

Return

None.

Throws

javax.mail.MessagingException

java.io.IOException

isMimeBodyPart

Description

Returns true if the part is a mime part, or false if it is URL encoded.

Syntax

```
public boolean isMimeBodyPart()
```

Parameters

None.

Returns

boolean

Returns true if the part is a mime part, otherwise, returns false.

Throws

None.

isMimeType

Description

Queries whether this part of the specified MIME type. This method compares only the primaryType and subType.

Syntax

```
public boolean isMimeType(java.lang.String typein)
```

Parameters

Name	Type	Description
typein	java.lang.String	The part to query.

Returns

boolean

Returns true if the part is a MIME type.

Throws

javax.mail.MessagingException

getDisposition

Description

Returns the content disposition parameter as a string.

Syntax

```
public java.lang.String getDisposition()
```

Parameters

None.

Return

java.lang.String

Returns the content disposition parameter as a string.

Throws

javax.mail.MessagingException

setDisposition

Description

Sets the disposition of the content type parameter.

Syntax

```
public void setDisposition(java.lang.String instr)
```

Parameters

Name	Type	Description
instr	java.lang.String	The content type to be set.

Return

None.

Throws

javax.mail.MessagingException

setContentID

Description

Sets the ContentID content type parameter.

Syntax

```
public void setContentID(java.lang.String instr)
```

Parameters

Name	Type	Description
instr	java.lang.String	The contentID to be set.

Return

None.

Throws

javax.mail.MessagingException

getContentID

Description

Gets the contentID content type parameter.

Syntax

```
public java.lang.String getContentID()
```

Parameters

None.

Return

java.lang.String

Returns the contentID content type parameter.

Throws

javax.mail.MessagingException

getContentTypeString

Description

Returns the contentType string.

Syntax

```
public java.lang.String getContentTypeString()
```

Parameters

None.

Return

java.lang.String

Returns the contentType string.

Throws

javax.mail.MessagingException

setContentMD5

Description

Sets the contentMD5 for this body part.

Syntax

```
public void setContentMD5(java.lang.String instr)
```

Parameters

Name	Type	Description
instr	java.lang.String	The contentMD5 to be set.

Return

None.

Throws

javax.mail.MessagingException

getContentMD5

Description

Gets the contentMD5 for this body part.

Syntax

```
public java.lang.String getContentMD5()
```

Parameters

None.

Return

java.lang.String
Returns the contentMD5 for this body part.

Throws

javax.mail.MessagingException

getDescription

Description

Gets the description of this body part.

Syntax

```
public java.lang.String getDescription()
```

Parameters

None.

Return

java.lang.String
Returns the description for the body part.

Throws

javax.mail.MessagingException

setDescription

Description

Sets the description of this body part.

Syntax

```
public void setDescription(java.lang.String instr)
    throws javax.mail.MessagingException
```

Parameters

Name	Type	Description
instr	java.lang.String	The description to be set.

Return

None.

Throws

javax.mail.MessagingException

getEncoding

Description

Gets the encoding of this body part.

Syntax

```
public java.lang.String getEncoding()
```

Parameters

None.

Return

java.lang.String
Returns the encoding for the body part.

Throws

javax.mail.MessagingException

getFileName

Description

Gets the filename parameter for this body part.

Syntax

```
public java.lang.String getFileName()
```

Parameters

None.

Return

java.lang.String

Returns the filename parameter for the body part.

Throws

javax.mail.MessagingException

setFileName

Description

Sets the filename of this body part.

Syntax

```
public void setFileName(java.lang.String instr)
```

Parameters

Name	Type	Description
instr	java.lang.String	The filename to be set.

Return

None.

Throws

javax.mail.MessagingException

getContentType

Description

Gets the content type as a webETDContentType object for this body part.

Syntax

```
public webETDContentType getContentType()
```

Parameters

None.

Return

webETDContentType

Returns the content type as a webETDContentType object for the body part.

Throws

javax.mail.MessagingException

countNestedMultiPart

Description

Counts the number of parts in a nested multipart.

Syntax

```
public int countNestedMultiPart()
```

Parameters

None.

Return

int

Returns the number of parts in the nested multipart form, if none, returns zero.

Throws

None.

getNestedMultiPart

Description

Returns the nested multipart.

Syntax

```
public OneMimeBodyPart getNestedMultiPart(int index)
```

Parameters

Name	Type	Description
index	int	The index number for the nested multipart to be returned.

Return

OneMimeBodyPart

Returns the nested multipart object.

Throws

None.

marshal

Description

Serializes this object into a byte array.

Syntax

```
public byte[] marshal(boolean buildmbponly)
```

Parameters

Name	Type	Description
buildmbponly	boolean	The object to be deserialized. The build MimeBodyPart does not return a byte array.

Return

byte[]

Returns a byte array corresponding to a deserialized OneMimeBodyPart object, else null.

Throws

com.stc.jcsre.MarshalException
javax.mail.MessagingException
java.io.IOException

unmarshal

Description

Deserializes the byte array passed into this object.

Syntax

```

public void unmarshal(byte[] abodyins)
    throws javax.mail.MessagingException,
           java.io.IOException

```

Parameters

Name	Type	Description
abodyins	byte[]	The byte array to be deserialized into a OneMimeBodyPart object.

Return

None.

Throws

javax.mail.MessagingException
java.io.IOException

5.5 Class OneMimeBodyPart.NestedMultiPart

```

com.stc.eways.webETD
Class OneMimeBodyPart.NestedMultiPart
java.lang.Object
    com.stc.eways.webETD.OneMimeBodyPart.NestedMultiPart

```

```
Enclosing class:OneMimeBodyPart
public class OneMimeBodyPart.NestedMultiPart
extends java.lang.Object
```

The `OneMimeBodyPart.NestedMultiPart` Class methods are described in detail on the following pages:

[OneMimeBodyPart.NestedMultiPart](#) on page 74 [getPart](#) on page 75
[setCurrIndex](#) on page 74 [unmarshal](#) on page 75
[getSize](#) on page 74

OneMimeBodyPart.NestedMultiPart

Description

Constructor.

Syntax

```
public OneMimeBodyPart.NestedMultiPart()
```

setCurrIndex

Description

Sets the current index point.

Syntax

```
public void setCurrIndex(int i)
```

Parameters

Name	Type	Description
i	int	The index number for the nested multipart to be set.

Return

None.

Throws

None.

getSize

Description

Gets the size.

Syntax

```
public int getSize()
```

Parameters

None.

Return

int

Returns the size of the object.

Throws

None.

getPart

Description

Gets the part.

Syntax

```
public OneMimeBodyPart getPart()
```

Parameters

None.

Return

OneMimeBodyPart

Returns the OneMimeBodyPart object.

Throws

None.

unmarshal

Description

Deserializes the byte array passed into this object.

Syntax

```
public void unmarshal(byte[] bytearraybodyin)
```

Parameters

Name	Type	Description
bytearraybodyin	byte[]	The byte array to be deserialized into a OneMimeBodyPart object.

Return

None.

Throws

```
com.stc.jcsre.UnmarshalException
javax.mail.MessagingException
java.io.IOException
```

5.6 Class webReplyETD

```
java.lang.Object
  com.stc.jcsre.StimpleETDImpl
    com.stc.jcsre.MsgETDImpl
      com.stc.eways.webETD.webReplyETD
All Implemented Interfaces: com.stc.jcsre.ETD,
com.stc.jcsre.ETDConstansts
public class webReplyETD
  extends com.stc.jcsre.MsgETDImpl
  implements com.stc.jcsre.ETD
```

The webReplyETD Class methods are described in detail on the following pages:

[webReplyETD](#) on page 76

[getJMSReplyTo](#) on page 76

[setJMSReplyTo](#) on page 77

[send](#) on page 77

[getBody](#) on page 78

[getContentType](#) on page 78

[addHeader](#) on page 79

[setHeader](#) on page 79

[getHeader](#) on page 79

[getMultiParts](#) on page 80

[isMultipart](#) on page 80

[countMultiParts](#) on page 81

[marshal](#) on page 81

webReplyETD

Description

Constructor.

Syntax

```
public webReplyETD()
```

getJMSReplyTo

Description

Gets the JMSReplyTo field. This is normally obtained from the corresponding webRequestETD.

Syntax

```
public java.lang.String getJMSReplyTo()
```

Parameters

None.

Returns

java.lang.String
Returns the JMSReplyTo field.

Throws

None.

setJMSReplyTo

Description

Sets the JMSReplyTo field. This is normally obtained from the corresponding webRequestETD.

Syntax

```
public void setJMSReplyTo(java.lang.String replyTo)
```

Parameters

Name	Type	Description
replyTo	java.lang.String	The JMSReplyTo field to set.

Returns

None.

Throws

None.

send

Description

Overrides the super's send() method to work with JMS. You must call setJMSReplyTo before call this method.

Syntax

```
public void send()
```

Parameters

None.

Return

None.

Throws

None.

Specified by

`send` in interface `com.stc.jcsre.ETD`

Overrides

`send` in class `com.stc.jcsre.MsgETDImpl`

getBody

Description

Gets the body of this reply, if the reply is of a discrete type (text/plain, image/jpeg).

Syntax

```
public Body getBody()
```

Parameters

None.

Return

Body

Returns the body of this reply if the reply is discrete type. For example, text/plain or image/jpeg.

Throws

None.

getContentType

Description

Gets the content type of this reply, as a `webETDContentType` object.

Syntax

```
public webETDContentType getContentType()
```

Parameters

None.

Returns

webETDContentType

Returns the `webETDContentType` object.

Throws

None.

addHeader

Description

Adds a name/value pair as a new header to this reply.

Syntax

```
public void addHeader (java.lang.String name, java.lang.String value)
```

Parameters

Name	Type	Description
name	java.lang.String	The name string
value	java.lang.String	The value string

Returns

None.

Throws

None.

setHeader

Description

Sets the name/value pair header. If the header name already exists, the associated value is overwritten.

Syntax

```
public void setHeader(java.lang.String name, java.lang.String value)
```

Parameters

Name	Type	Description
name	java.lang.String	The name of the header to set.
value	java.lang.String	The value to set for the header.

Returns

None.

Throws

None.

getHeader

Description

Gets the first header line by the name and delimiter.

Syntax

```
public java.lang.String getHeader(java.lang.String name,  
    java.lang.String delim)
```

Parameters

Name	Type	Description
name	java.lang.String	The name of the header to get.
delim	java.lang.String	The delimiter.

Returns

java.lang.String

Returns the first header line value.

Throws

None.

getMultiParts

Description

Gets the value for the indexed part, provided it is multipart data.

Syntax

```
public OneMimeBodyPart getMultiParts(int index)
```

Parameters

Name	Type	Description
index	int	The index point for the part.

Returns

OneMimeBodyPart

Returns the value for the part.

Throws

None.

isMultipart

Description

Queries whether the request, originated as multipart data.

Syntax

```
public boolean isMultipart()
```

Parameters

None.

Returns

boolean

Returns true if the request originated as multipart data.

Throws

None.

countMultiParts

Description

Counts the number of parts contained in the multipart body.

Syntax

```
public int countMultiParts()
```

Parameters

None.

Returns

int

Returns the number of parts.

Throws

None.

marshal

Description

Serializes the object into a byte array.

Syntax

```
public byte[] marshal()
```

Parameters

None.

Returns

byte array

Returns a byte array of the serialized object.

Throws

`com.stc.jcsre.MarshalException`

Specified by

`marshal` in interface `com.stc.jcsre.ETD`

Overrides

`marshal` in class `com.stc.jcsre.SimpleETDImpl`

5.7 Class webRequestETD

```
java.lang.Object
  com.stc.jcsre.SimpleETDImpl
    com.stc.jcsre.MsgETDImpl
      com.stc.eways.webETD.webRequestETD
All Implemented Interfaces:
com.stc.jcsre.ETD, com.stc.jcsre.ETDConstants
public class webRequestETD
  extends com.stc.jcsre.MsgETDImpl
  implements com.stc.jcsre.ETD
```

The webRequestETD Class methods are described in detail on the following pages:

[webRequestETD](#) on page 82

[getJMSReplyTo](#) on page 82

[getContentType](#) on page 83

[getRequestMethod](#) on page 83

[getEnvironmentVariables](#) on page 84

[countEnvironmentVariables](#) on page 84

[getURLNameValueQueryPairs](#) on page 85

[isSingleBody](#) on page 85

[getBody](#) on page 85

[isUrlencoded](#) on page 86

[countURLNameValueQueryPairs](#) on page 86

[getMultiParts](#) on page 87

[isMultipart](#) on page 87

[countMultiParts](#) on page 87

[unmarshal](#) on page 88

webRequestETD

Description

Constructor.

Syntax

```
public webRequestETD()
```

getJMSReplyTo

Description

Gets the JMSReplyTo for this Event.

Syntax

```
public java.lang.String getJMSReplyTo()
```

Parameters

None.

Returns

java.lang.String
Returns JMSReplyTo string.

Throws

None.

getContentType

Description

Gets the ContentType object.

Syntax

```
public webETDContentType getContentType()
```

Parameters

None.

Returns

webETDContentType
Returns webETDContentType object.

Throws

None.

getRequestMethod

Description

Gets request method string.

Syntax

```
public java.lang.String getRequestMethod()
```

Parameters

None.

Returns

java.lang.String
Returns the request method string.

Throws

None.

getEnvironmentVariables

Description

Gets the environment variables object.

Syntax

```
public webRequestETD.EnvironmentVariables getEnvironmentVariables(int  
index)
```

Parameters

Name	Type	Description
index	int	The index point.

Returns

webRequestETD.EnvironmentVariables

Returns the webRequestETD.EnvironmentVariable object.

Throws

None.

countEnvironmentVariables

Description

Counts the number of environment variables that are part of the JMS property passed in. Each environment variable is a name value pair. For example, SERVER_PROTOCOL=HTTP/1.1.

Syntax

```
public int countEnvironmentVariables()
```

Parameters

None.

Returns

int

Returns the number of environment variables.

Throws

None.

getURLNameValueQueryPairs

Description

Gets the specified name/value pair, URL decoded.

Syntax

```
public webRequestETD.URLNameValueQueryPairs  
getURLNameValueQueryPairs(int index)
```

Parameters

Name	Type	Description
index	int	The index point.

Returns

webRequestETD.URLNameValueQueryPairs
Returns the specified name/value pair.

Throws

None.

isSingleBody

Description

Queries whether the request originated as Application/x-www-urlencoded data.

Syntax

```
public boolean isSingleBody()
```

Parameters

None.

Returns

boolean
Returns true if the original request was sent in Application/x-www-urlencoded format.

Throws

None.

getBody

Description

Gets the body of this webRequestETD, provided the content type is discrete (text/plain or image/jpeg).

Syntax

```
public Body getBody()
```

Parameters

None.

Returns

Body

Returns the body of the webRequestETD.

Throws

None.

isUrlencoded

Description

Queries whether the HTTP request (GET) is URL encoded.

Syntax

```
public boolean isUrlencoded()
```

Parameters

None.

Return Value

boolean

Returns true to indicate that the HTTP request (GET) is URL encoded.

Throws

None.

countURLNameValueQueryPairs

Description

Counts the number of environment variables.

Syntax

```
public int countURLNameValueQueryPairs()
```

Parameters

None.

Return Value

int

Returns the number of environment variables.

Throws

None.

getMultiParts

Description

Gets the specified part.

Syntax

```
public OneMimeBodyPart getMultiParts(int index)
```

Parameters

Name	Type	Description
index	int	The index point.

Returns

OneMimeBodyPart

Returns the OneMimeBodyPart object.

Throws

None.

isMultipart

Description

Queries whether the request originated as Multipart/form-data.

Syntax

```
public boolean isMultipart()
```

Parameters

None.

Returns

boolean

Returns true if the request originated as Multipart/form-data.

Throws

None.

countMultiParts

Description

Counts the number of MIME parts.

Syntax

```
public int countMultiParts()
```

Parameters

None.

Returns

int

Returns the number of MIME parts.

Throws

None.

unmarshal**Description**

Deserializes the byte array passed into this object.

Syntax

```
public void unmarshal(byte[] inputEvent)
    throws com.stc.jcsre.UnmarshalException
```

Parameters

Name	Type	Description
inputEvent	byte array	The input Event to be deserialized.

Returns

None.

Throws

com.stc.jcsre.MarshalException

Specified by

unmarshal in interface **com.stc.jcsre.ETD**

Overrides

unmarshal in class **com.stc.jcsre.SimpleETDImpl**

5.8 Class webETDContentType

```
com.stc.eways.webETD
java.lang.Object
    com.stc.eways.webETD.webETDContentType
public class webETDContentType
    extends java.lang.Object
```

The webETD Class methods are described in detail on the following pages:

[webETDContentType](#) on page 89

[setCharSet](#) on page 92

[unmarshal](#) on page 89

[toString](#) on page 89

[getPrimaryType](#) on page 90

[setPrimaryType](#) on page 90

[getSubType](#) on page 91

[setSubType](#) on page 91

[getCharSet](#) on page 91

[getMultipartBoundary](#) on page 92

[setMultipartBoundary](#) on page 93

[getContentTransferEncoding](#) on page 93

[setContentTransferEncoding](#) on page 93

[getContentTypeParameter](#) on page 94

[setContentTypeParameter](#) on page 94

[marshal](#) on page 97

webETDContentType

Description

Constructor.

Syntax

```
public webETDContentType()
```

unmarshal

Description

Deserializes an object input put as a string.

Syntax

```
public void unmarshal(java.lang.String instr)
```

Parameters

Name	Type	Description
instr	java.lang.String	The input as a string.

Returns

None.

Throws

javax.mail.internet.ParseException

toString

Description

Returns a string representation of the object.

Syntax

```
public java.lang.String toString()
```

Parameters

None.

Returns

java.lang.String

Returns a string representation of the object.

Throws

None.

Overrides

toString in class **java.lang.Object**

getPrimaryType

Description

Gets the primary type in a media type, such as, text in text/plain.

Syntax

```
public java.lang.String getPrimaryType()
```

Parameters

None.

Returns

java.lang.String

Returns the primary type as a string.

Throws

None.

setPrimaryType

Description

Sets the primary type in the object. For example, text in text/plain.

Syntax

```
public void setPrimaryType(java.lang.String instr)
```

Parameters

Name	Type	Description
instr	java.lang.String	The primary type to set.

Return Value

None.

Throws

None.

getSubType**Description**

Gets the sub type in media type. For example, plain in text/plain.

Syntax

```
public java.lang.String getSubType()
```

Parameters

None.

Returns

java.lang.String

Returns the sub type in a media type.

Throws

None.

setSubType**Description**

Sets the sub type in the object. For example, plain in text/plain.

Syntax

```
public void setSubType(java.lang.String instr)
```

Parameters

Name	Type	Description
instr	java.lang.String	The sub type to set.

Returns

None.

Throws

None.

getCharSet**Description**

Gets the charSet in a media type. For example, EUC_JP.

Syntax

```
public java.lang.String getCharSet()
```

Parameters

None.

Returns

java.lang.String
Returns the charSet value.

Throws

None.

setCharSet**Description**

Sets the charSet in a media type. For example, EUC_JP.

Syntax

```
public void setCharSet(java.lang.String instr)
```

Parameters

Name	Type	Description
instr	java.lang.String	The charSet type to set.

Returns

None.

Throws

None.

getMultipartBoundary**Description**

Gets the boundary parameter for a content type.

Syntax

```
public java.lang.String getMultipartBoundary()
```

Parameters

None.

Returns

java.lang.String
Returns the boundary parameter.

Throws

None.

setMultipartBoundary**Description**

Sets the boundary parameter in a content type.

Syntax

```
public void setMultipartBoundary(java.lang.String instr)
```

Parameters

Name	Type	Description
instr	java.lang.String	The boundary to set.

Returns

None.

Throws

None.

getContentTypeEncoding**Description**

Gets the content transfer encoding parameter for a content type. For example, base64.

Syntax

```
public java.lang.String getContentTypeEncoding()
```

Parameters

None.

Returns

java.lang.String

Returns the content transfer encoding parameter.

Throws

None.

setContentTypeEncoding**Description**

Sets the content transfer encoding parameter in a content type. For example, base64.

Syntax

```
public void setContentTransferEncoding(java.lang.String instr)
```

Parameters

Name	Type	Description
instr	java.lang.String	The content transfer encoding to set.

Returns

None.

Throws

None.

getContentParameter

Description

Gets a specified parameter in a content type. For example, ContentID.

Syntax

```
public java.lang.String getContentParameter(java.lang.String nm)
```

Parameters

Name	Type	Description
nm	java.lang.String	The name of the parameter to get.

Returns

java.lang.String
Returns a parameter as a string.

Throws

None.

setContentParameter

Description

Sets the parameter value in a content type. For example, ContentID.

Syntax

```
public void setContentParameter(java.lang.String nm,  
                               java.lang.String val)
```

Parameters

Name	Type	Description
nm	java.lang.String	The name of the parameter to set.
val	java.lang.String	The value to be set.

Returns

None.

Throws

None.

marshal

Description

Serializes the object into a byte array.

Syntax

```
public byte[] marshal()
```

Parameters

None.

Returns

byte array

Returns a byte array of the serialized object.

Throws

com.stc.jcsre.MarshalException

5.9 Class webETDInternetHeaders

```
com.stc.eways.webETD
java.lang.Object
    com.stc.eways.webETD.webETDInternetHeaders
public class webETDInternetHeaders
    extends java.lang.Object
```

webETDInternetHeaders

Description

Constructors.

Syntax

```
public webETDInternetHeaders()
```

addHeader

Description

Adds a name/value pair header. The delimiter is set by default.

Syntax

```
public void addHeader(java.lang.String nm,  
                     java.lang.String val)
```

Parameters

Name	Type	Description
nm	java.lang.String	The name of the parameter to set.
val	java.lang.String	The value to be set.

Returns

None.

Throws

None.

setHeader

Description

Sets a name/value pair header delimiter. If the header already exists, it is overwritten.

Syntax

```
public void setHeader(java.lang.String name,  
                    java.lang.String value)
```

Parameters

Name	Type	Description
name	java.lang.String	The name of the parameter to set.
value	java.lang.String	The value to be set.

Returns

None.

Throws

None.

getHeader

Description

Gets the value of a header and delimiter. If multiple header lines match, the first one is returned.

Syntax

```
public java.lang.String getHeader(java.lang.String nm,  
                                 java.lang.String delim)
```

Parameters

Name	Type	Description
nm	java.lang.String	The name of the parameter to get.
delim	java.lang.String	The delimiter to get.

Returns

java.lang.String

Returns the value of a header and delimiter. If multiple header lines match, the first one is returned.

Throws

None.

getAsInternetHeaders

Description

Gets the headers as internet headers.

Syntax

```
public javax.mail.internet.InternetHeaders getAsInternetHeaders()
```

Parameters

None.

Returns

javax.mail.internet

Returns the headers as javax.mail.internet.InternetHeaders.

Throws

None.

marshal

Description

Serializes the object into a byte array.

Syntax

```
public byte[] marshal()
```

Parameters

None.

Returns**byte array**

Returns a byte array of the serialized object.

Throws

com.stc.jcsre.MarshalException

5.10 Class webReplyETD.ReplyMultiParts

```
com.stc.eways.webETD
java.lang.Object
  com.stc.eways.webETD.webReplyETD.ReplyMultiParts
Enclosing class:
webReplyETD
  public class webReplyETD.ReplyMultiParts
  extends java.lang.Object
```

The webReplyETD.ReplyMultiParts Class methods are described in detail on the following pages:

[webReplyETD.ReplyMultiParts](#) on page 98

[getPart](#) on page 99

[setCurrIndex](#) on page 98

[marshal](#) on page 100

[getSize](#) on page 99

webReplyETD.ReplyMultiParts

Description

Constructor.

Syntax

```
public webReplyETD.ReplyMultiParts()
```

setCurrIndex

Description

Sets the current index.

Syntax

```
public void setCurrIndex(int i)
```

Parameters

Name	Type	Description
i	int	The index point to set.

Returns

None.

Throws

None.

getSize

Description

Gets the size of the part.

Syntax

```
public int getSize()
```

Parameters

None.

Returns

int
Returns the size of the part.

Throws

None.

getPart

Description

Gets the OneMimeBodyPart object.

Syntax

```
public OneMimeBodyPart getPart()
```

Parameters

None.

Returns

OneMimeBodyPart
Returns the OneMimeBodyPart object.

Throws

None.

marshal

Description

Serializes the object into a byte array, based on the content type.

Syntax

```
public byte[] marshal(webETDContentType topcontenttype)
```

Parameters

Name	Type	Description
topcontenttype	webETDContentType	The webETDContentType object.

Returns

byte array

Returns a byte array of the serialized object.

Throws

`com.stc.jcsre.MarshalException`

5.11 Class webRequestETD.EnvironmentVariables

```
com.stc.eways.webETD
java.lang.Object
    com.stc.eways.webETD.webRequestETD.EnvironmentVariables
Enclosing class:
    webRequestETD
public class webRequestETD.EnvironmentVariables
    extends java.lang.Object
```

The webRequestETD.EnvironmentVariables Class methods are described in detail on the following pages:

[webRequestETD.EnvironmentVariables](#) on page 100 [getSize](#) on page 101
[setCurrIndex](#) on page 101 [getName](#) on page 102
[addEnvVarPair](#) on page 101 [getValue](#) on page 102

webRequestETD.EnvironmentVariables

Description

Constructor.

Syntax

```
public webRequestETD.EnvironmentVariables()
```

setCurrIndex

Description

Sets the current index point.

Syntax

```
public void setCurrIndex(int i)
```

Parameters

Name	Type	Description
i	int	The index point to set.

Returns

None.

Throws

None.

addEnvVarPair

Description

Adds an Environmental variable pair.

Syntax

```
protected void addEnvVarPair(NameValue newpair)
```

Parameters

Name	Type	Description
newpair	NameValue	The name value object to be added.

Returns

None.

Throws

None.

getSize

Description

Gets the size of the variable.

Syntax

```
public int getSize()
```

Parameters

None.

Returns

int

Returns the size of the variable.

Throws

None.

getName

Description

Gets the name of the variable.

Syntax

```
public java.lang.String getName()
```

Parameters

None.

Returns

java.lang.String

Returns the name of this environment variable.

Throws

None.

getValue

Description

Gets the value of the variable.

Syntax

```
public java.lang.String getValue()
```

Parameters

None.

Returns

java.lang.String

Returns the value for the environment variable.

Throws

None.

5.12 Class webRequestETD.MultiParts

```
com.stc.eways.webETD
java.lang.Object
    com.stc.eways.webETD.webRequestETD.MultiParts
Enclosing class:
webRequestETD
public class webRequestETD.MultiParts
    extends java.lang.Object
```

The webRequestETD.MultiParts Class methods are described in detail on the following pages:

[webRequestETD.MultiParts](#) on page 103 [unmarshal](#) on page 104

[setCurrIndex](#) on page 103 [getPart](#) on page 104

[getSize](#) on page 104

webRequestETD.MultiParts

Description

Constructor.

Syntax

```
public webRequestETD.MultiParts()
```

setCurrIndex

Description

Sets the current index point.

Syntax

```
public void setCurrIndex(int i)
```

Parameters

Name	Type	Description
i	int	The index point to set.

Returns

None.

Throws

None.

getSize

Description

Gets the size of the part.

Syntax

```
public int getSize()
```

Parameters

None.

Returns

int
Returns the size of the part.

Throws

None.

unmarshal

Description

Deserializes the byte array passed into this object.

Syntax

```
public void unmarshal(byte[] bytearraybodyin)
```

Parameters

Name	Type	Description
bytearraybodyin	byte array	The object to be deserialized.

Returns

None.

Throws

com.stc.jcsre.UnmarshalException
java.io.IOException
javax.mail.MessagingException

getPart

Description

Gets the part.

Syntax

```
public OneMimeBodyPart getPart()
```

Parameters

None.

Returns**OneMimeBodyPart**

Returns the OneMimeBodyPart object.

Throws

None.

5.13 Class webRequestETD.URLNameValueQueryPairs

```
com.stc.eways.webETD
java.lang.Object
    com.stc.eways.webETD.webRequestETD.URLNameValueQueryPairs
Enclosing class:
webRequestETD
public class webRequestETD.URLNameValueQueryPairs
    extends java.lang.Object
```

The webRequestETD.IURLNameValueQueryPairs Class methods are described in detail on the following pages:

[webRequestETD.URLNameValueQueryPairs](#) [getValue](#) on page 106
on page 105

[getSize](#) on page 105 [setCurrIndex](#) on page 107

[getName](#) on page 106 [unmarshal](#) on page 107

webRequestETD.URLNameValueQueryPairs

Description

Constructor.

Syntax

```
public webRequestETD.URLNameValueQueryPairs()
```

getSize

Description

Gets the size of the name/value pair.

Syntax

```
public int getSize()
```

Parameters

None.

Returns

int
Returns the size of the name/value pair.

Throws

None.

getName

Description

Gets the name of the name/value pair.

Syntax

```
public java.lang.String getName()
```

Parameters

None.

Returns

java.lang.String
Returns the name of the name/value pair.

Throws

None.

getValue

Description

Gets the value for the name/value pair.

Syntax

```
public java.lang.String getValue()
```

Parameters

None.

Returns

java.lang.String
Returns the value for the name/value pair.

Throws

None.

setCurrIndex

Description

Sets the current index point.

Syntax

```
public void setCurrIndex(int i)
```

Parameters

Name	Type	Description
i	int	The index point to set.

Returns

None.

Throws

None.

unmarshal

Description

Separates the URL encoded string into name/value pairs.

Syntax

```
public void unmarshal(java.lang.String urlencodedstring)
```

Parameters

Name	Type	Description
urlencodedstring	java.lang.String	The string to be broken down into a name/value pair.

Returns

None.

Throws

com.stc.jcsre.UnmarshalException

Index

A

addEnvVarPair 101
addHeader 79, 96

B

Body 56

C

CGI Data Section 29
 EnvEnd 29
 EnvInBody 29
 EnvsAsProps 29
 ReadChunksize 30
 WriteChunksize 30

Class

 Body 55
 Body 56
 getRawPayload 56
 getTextStringPayload 58
 getTransferCodePayload 57
 marshal 58
 setRawPayload 56
 setTextStringPayload 58
 setTransferCodePayload 57
 unmarshal 59
 NameValue 59
 getName 60
 getValue 60
 marshal 61
 NameValue 60
 setIsURLEncoded 61
 unmarshal 62
 OneMimeBodyart
 getDescription 69
 OneMimeBodyPart 62
 countNestedMultiPart 72
 getContentID 68
 getContentMD5 69
 getContentType 71
 getContentTypeString 68
 getDisposition 66
 getEncoding 70

 getFileName 70
 getMimeBodyPart 63
 getMimeBodyPartDecodedPayload 64
 getMimeBodyPartRawPayload 63
 getMimeBodyPartTextStringPayload 65
 getNestedMultiPart 72
 isMimeBodyPart 65
 isMimeType 66
 marshal 72
 OneMimeBodyPart 63
 setContentID 67
 setContentMD5 68
 setDescription 70
 setDisposition 67
 setFileName 71
 setMimeBodyPartRawPayload 64
 setMimeBodyPartTextStringPayload 65
 unmarshal 73

 OneMimeBodyPart.NestedMultiPart 73
 getPart 75
 getSize 74
 OneMimeBodyPart.NestedMultiPart 74
 setCurrIndex 74
 unmarshal 75

 webETDContentType 88

 getCharSet 91
 getContentTransferEncoding 93
 getContentTypeParameter 94
 getMultipartBoundary 92
 getPrimaryType 90
 getSubType 91
 marshal 95
 setCharSet 92
 setContentTransferEncoding 93
 setContentTypeParameter 94
 setMultipartBoundary 93
 setPrimaryType 90
 setSubType 91
 toString 89
 unmarshal 89
 webETDContentType 89

 webETDInternetHeaders 95

 addHeader 96
 getAsInternetHeaders 97
 getHeader 97
 marshal 97
 setHeader 96
 webETDInternetHeaders 95

 webReplyETD 76

 addHeader 79
 countMultiPart 81
 getBody 78
 getContentType 78
 getHeader 79

- getJMSReplyTo 76
 - getMultiParts 80
 - isMultipart 80
 - marshal 81
 - send 77
 - setHeader 79
 - setJMSReplyTo 77
 - webReplyETD 76
 - webReplyETD.ReplyMultiParts 98
 - getPart 99
 - getSize 99
 - marshal 100
 - setCurrIndex 98
 - webReplyETD.ReplyMultiParts 98
 - webRequestETD 82
 - countEnvironmentVariables 84
 - countMultiParts 87
 - countURLNameValueQueryPairs 86
 - getBody 85
 - getContentType 83
 - getEnvironmentVariables 84
 - getJMSReplyTo 82
 - getMultiParts 87
 - getRequestMethod 83
 - getURLNameValueQueryPairs 85
 - isMultipart 87
 - isSingleBody 85
 - isUrlencoded 86
 - unmarshal 88
 - webRequestETD 82
 - webRequestETD.EnvironmentVariables 100
 - addEnvVarPair 101
 - getName 102
 - getSize 101
 - getValue 102
 - setCurrIndex 101
 - webRequestETD.EnvironmentVariables 100
 - webRequestETD.MultiParts 103
 - getPart 104
 - getSize 104
 - setCurrIndex 103
 - unmarshal 104
 - webRequestETD.MultiParts 103
 - webRequestETD.URLNameValueQueryPairs 105
 - getName 106
 - getSize 105
 - getValue 106
 - setCurrIndex 107
 - unmarshal 107
 - webRequestETD.URLNameValueQueryPairs 105
 - Classpath Override 20
 - Classpath Prepend 20
 - ClientID 29
 - components 9
 - configuring the participating host 16
 - configuring the web server 23
 - countEnvironmentVariables 84
 - countMultiParts 81, 87
 - countNestedMultiPart 72
 - countURLNameValueQueryPairs 86
- ## D
- Disable JIT 22
- ## E
- EnvEnd 29
 - EnvInBody 29
 - EnvsAsProps 29
 - ETDs, sample 45
 - Event Type Definitions, sample 45
- ## F
- files created by installation procedure 14
 - files/directories created by install 14
- ## G
- getAsInternetHeaders 97
 - getBody 78, 85
 - getCharSet 91
 - getContentID 68
 - getContentMD5 69
 - getContentTransferEncoding 93
 - getContentType 71, 78, 83
 - getContentTypeParameter 94
 - getContentTypeString 68
 - getDescription 69
 - getDisposition 66
 - getEncoding 70
 - getEnvironmentVariables 84
 - getFileName 70
 - getHeader 79, 97
 - getJMSReplyTo 76, 82
 - getMimeBodyPart 63
 - getMimeBodyPartDecodedPayload 64
 - getMimeBodyPartRawPayload 63
 - getMimeBodyPartTextStringPayload 65
 - getMultipartBoundary 92
 - getMultiParts 80, 87
 - getName 60, 102, 106
 - getNestedMultiPart 72
 - getPart 75, 99, 104

getPrimaryType 90
getRawPayload 56
getRequestMethod 83
getSize 74, 99, 101, 104, 105
getSubType 91
getTextStringPayload 58
getTransferCodePayload 57
getURLNameValueQueryPairs 85
getValue 60, 102, 106

H

Host 28

I

Initial Heap Size 21
installation
 files/directories created 14
installing the CGI e*Way 11
intended reader 8
isMimeBodyPart 65
isMimeType 66
isMultipart 80, 87
isSingleBody 85
isUrlencoded 86

J

JMS Connection Section
 ClientID 29
 Host 28
 Port 28
 Queue 29
 RequestReply 28
 Timeout 28
 Topic 29
 TopicRequest 29
JNI DLL Absolute Pathname 19
JVM settings 19

L

Log Section 31
 LogFile 31
 Trace 31
LogFile 31

M

marshal 58, 61, 72, 81, 95, 97, 100
Maximum Heap Size 21
mscgi.properties

CGI Data Section 29
JMS Connection Section 28
Log Section 31
Multi-Mode e*Way
 configuration 18
 configuration parameters 19
 Auxiliary JVM Configuration File 22
 CLASSPATH Append From Environment Variable 21
 CLASSPATH Override 20
 CLASSPATH Prepend 20
 Disable JIT 22
 JNI DLL Absolute Pathname 19
 Maximum Heap Size 21
 Maximum Stack Size for JVM Threads 21
 Maximum Stack Size for Native Threads 21
 Remote Debugging port number 22
 Suspend option for debugging 22
 creating 18
 parameters 19

N

NameValue 59, 60

O

OneMimeBodyPart 62, 63
OneMimeBodyPart.NestedMultiPart 74

P

parameters
 Multi-Mode e*Way
 CLASSPATH prepend 20
 Initial Heap Size 21
 JNI DLL absolute pathname 19
 JVM settings 19
 Maximum Heap Size 21
Port 28
product overview 8

Q

Queue 29

R

ReadChunksize 30
RequestReply 28

S

- send 77
- setCharSet 92
- setContentID 67
- setContentMD5 68
- setContentTransferEncoding 93
- setContentDispositionParameter 94
- setCurrIndex 74, 98, 101, 103, 107
- setDescription 70
- setDisposition 67
- setFileName 71
- setHeader 79, 96
- setIsURLEncoded 61
- setJMSReplyTo 77
- setMimeBodyPartRawPayload 64
- setMimeBodyPartTextStringPayload 65
- setMultipartBoundary 93
- setPrimaryType 90
- setRawPayload 56
- setSubType 91
- setTextStringPayload 58
- setTransferCodePayload 57
- Supporting Documents 11
- system requirements 10

T

- Timeout 28
- Topic 29
- TopicRequest 29
- toString 89
- Trace 31

U

- Unix install 13
- unmarshal 59, 62, 73, 75, 88, 89, 104, 107

W

- webETDContentType 89
- webETDInternetHeaders 95
- webReplyETD 76
- webReplyETD.ReplyMultiParts 98
- webRequestETD 82
- webRequestETD.EnvironmentVariables 100
- webRequestETD.MultiParts 103
- webRequestETD.URLNameValueQueryPairs 105
- Windows NT install 12
- WriteChunksize 30