

***SeeBeyond ICAN Suite***

# **IMS eWay Intelligent Adapter User's Guide**

***Release 5.0.3***



The information contained in this document is subject to change and is updated periodically to reflect changes to the applicable software. Although every effort has been made to ensure the accuracy of this document, SeeBeyond Technology Corporation (SeeBeyond) assumes no responsibility for any errors that may appear herein. The software described in this document is furnished under a License Agreement and may be used or copied only in accordance with the terms of such License Agreement. Printing, copying, or reproducing this document in any fashion is prohibited except in accordance with the License Agreement. The contents of this document are designated as being confidential and proprietary; are considered to be trade secrets of SeeBeyond; and may be used only in accordance with the License Agreement, as protected and enforceable by law. SeeBeyond assumes no responsibility for the use or reliability of its software on platforms that are not supported by SeeBeyond.

SeeBeyond, e\*Gate, and e\*Way are the registered trademarks of SeeBeyond Technology Corporation in the United States and select foreign countries; the SeeBeyond logo, e\*Insight, and e\*Xchange are trademarks of SeeBeyond Technology Corporation. The absence of a trademark from this list does not constitute a waiver of SeeBeyond Technology Corporation's intellectual property rights concerning that trademark. This document may contain references to other company, brand, and product names. These company, brand, and product names are used herein for identification purposes only and may be the trademarks of their respective owners.

© 2003 - 2004 by SeeBeyond Technology Corporation. All Rights Reserved. This work is protected as an unpublished work under the copyright laws.

**This work is confidential and proprietary information of SeeBeyond and must be maintained in strict confidence.**

Version 20040226174734.

# Contents

---

## Chapter 1

<b>Introducing the IMS eWay</b>	<b>7</b>
<b>Overview</b>	<b>7</b>
Information Management System (IMS)	7
The eWay Intelligent Adapter for IMS	7
<b>Supported Operating Systems</b>	<b>8</b>
<b>System Requirements</b>	<b>9</b>
<b>External System Requirements</b>	<b>9</b>
Software Requirements	9
Software Requirements for IMS Connect:	9

---

## Chapter 2

<b>Installing the IMS eWay</b>	<b>10</b>
<b>Installing the IMS eWay</b>	<b>10</b>
Before installing the eWay	10
Installing the IMS eWay on an eGate supported system	10
After Installation	11

---

## Chapter 3

<b>Configuring the eWay Properties</b>	<b>12</b>
<b>Creating and Configuring the IMS eWay</b>	<b>12</b>
Selecting IMS as the External Application	12
Creating Custom Properties for an IMS eWay	13
Using the Properties Sheet	13
<b>IMS eWay Connectivity Map Properties</b>	<b>15</b>
Connector	15
Class	15
Property.Tag	15
Type	16
<b>IMS eWay Environment Explorer Configuration Parameters</b>	<b>16</b>
TCPIP Configuration	16
Port	16
Server	16

IRM Header	17
IRM_CLIENTID	17
IRM_DESTID	17
IRM_F1 (MFS MOD Names)	18
IRM_F2 (COMMIT MODE)	18
IRM_F3 (Sync Level)	18
IRM_F4 (ACK/NAK/ Response)	19
IRM_F5 (Flow Control)	19
IRM_ID	20
IRM_LEN	20
IRM_LTERM	20
IRM_RACF_GRNAME	20
IRM_RACF_PW	21
IRM_RACF_USERID	21
IRM_SOCT	21
IRM_TIMER	21
IRM_TRNCOD	22
IRM_TRNCOD_SRC	22

---

## Chapter 4

<b>Using the IMS eWay With eInsight</b>	<b>23</b>
eInsight Engine and Components	23
The IMS eWay With eInsight	24
IMS eWay Considerations	24
IMS eWay eInsight Sample Project	24
Importing a Sample Project	25
The IMS_BP_Sample Project	25
Creating a Project	25
Creating a Business Process	26
Creating the Business Process Flow	26
Configuring the Modeling Elements	28
Creating a Connectivity Map	29
Selecting the External Applications	29
Populating the Connectivity Map	30
Binding the eWay Components	31
Creating an Environment	32
Configuring the eWays	33
Configuring the File eWays	33
Configuring the IMS eWay	34
Creating and Activating the Deployment Profile	35
Running the Project	36
Alerting and Logging	37

## Chapter 5

<b>Implementing an IMS eWay Project</b>	<b>38</b>
IMS eWay Components	38
IMS eWay Considerations	39
IMS eWay Sample Projects	39
Importing a Sample Project	39
<b>The IMS_JCE_Sample Project</b>	<b>40</b>
Create a Project	40
Create a Connectivity Map	41
Select the External Applications	41
Populate the Connectivity Map	41
Creating the Collaboration Definitions	42
The IMS_Collab Collaboration (Java)	42
Using the Collaboration Editor (Java)	43
Creating the IMS_Java_Collab Collaboration	43
Creating Collaboration Bindings	47
Creating an Environment	49
Configure the eWays	50
Configuring the IMS eWay	50
Creating and Activating the Deployment Profile	52
Running the Project	53
Alerting and Logging	53
<b>The IMS_MFS_Sample Project</b>	<b>54</b>
Create a project	54
Create a Connectivity Map	54
Select the External Applications	54
Populate the Connectivity Map	54
Create an OTD Using the IMS MFS Wizard	55
Create the Collaboration Definitions	56
The JavaCollaborationMFS Collaboration	56
The IMS_MFS_Collab Business Rules	57
Creating Collaboration Bindings	58
Configure the eWays	59
Creating an Environment	60
Creating and Activating the Deployment Profile	61
Running the Project	61
<b>The MFS_IMS_Sample Project</b>	<b>63</b>
Importing the MFS_IMS_Sample Project	63
Creating the Environment	63
Configure the eWays	64
Configuring the IMS eWay	65
Creating and Activating the Deployment Profile	65
Running the Project	66

Chapter 6

**Java Methods and Classes for the IMS eWay** **67**

**The IMSClientETD Class** **67**  
IMS Javadoc 67

**Index** **68**

# Introducing the IMS eWay

This document describes how to install and configure the IMS eWay Intelligent Adapter (called the IMS eWay throughout this document), as well as how to implement the eWay in a typical eGate environment.

This chapter provides a brief overview of operations and components, general features, and system requirements of the IMS eWay.

### Chapter Topics

- [Overview](#) on page 7
- [Supported Operating Systems](#) on page 8
- [System Requirements](#) on page 9
- [External System Requirements](#) on page 9

---

## 1.1 Overview


### 1.1.1. Information Management System (IMS)

IBM's IMS (Information Management System), is a database and transaction management system that provides an interface for users to access information in various databases via on-line transactions. IMS/TM (Transaction Manager), a message-based transaction processor, handles the execution of specific business application programs. IMS/DB (Database) is an entirely separate component providing access to the IMS hierarchical database from applications running under the IMS Transaction Manager, as well as IMS transaction monitor and OS/390 batch jobs.

### 1.1.2. The eWay Intelligent Adapter for IMS

The IMS eWay enables eGate to connect with IBM's IMS/TM mainframe applications through IBM's IMS Connect. (See [Figure 1 on page 8](#)).

**Figure 1** IMS eWay and the IMS Environment.



The eWay provides access to the Input and Output Descriptors (MID/MOD) of the IMS applications without requiring changes to the application. By capturing the field contents before screen formatting, the eWay is not affected by cosmetic changes to the application's screen design.

The eWay includes the IMS MFS Wizard conversion utility to facilitate the creation of input and output Object Type Definitions (OTDs) from IMS Message Format Service (MFS) files.

The implementation of the IMS eWay is in accordance with the IBM *IMS Connect Guide and Reference*. These documents describe the OTMA protocol and contain important prerequisite information for the configuration IMS Connect on the mainframe.

A sample project for the IMS eWay is included on the installation CD-ROM which demonstrates how a non-conversational scenario (simple send/response) is managed.

---

## 1.2 Supported Operating Systems

The IMS eWay is available for the following operating systems:

- Windows XP, Windows 2000, and Windows Server 2003
- Solaris 8 and 9
- AIX 5.1 and 5.2
- HP-UX 11.0 and 11i (RISC)
- HP Tru64 V5.1A
- Red Hat Linux 8 (Intel)
- Red Hat Linux Advanced Server 2.1 (Intel)



---

## 1.3 System Requirements

To set up and run the IMS eWay with the eGate Enterprise Designer, you need the following:

- A TCP/IP network connection.
- Windows Server 2003, Windows 2000, or Windows XP. This is required for the User Interface.
- Microsoft Internet Explorer 6.0 or above.

**Note:** *Open and review the **Readme.txt** prior to installation for any additional requirements.*

---

## 1.4 External System Requirements

### Software Requirements

- IMS Connect, Version 2.1 and above.

**Note:** *IMS Connect is an optional and priced companion product to IMS. IMS Connect is not included with IMS.*

### Software Requirements for IMS Connect:

- z/OS Version 1 Release 2, z/OS Version 1 Release 3, z/OS Version 1 Release 4.
- IMS Version 7, with the required maintenance APARs applied. See IMS Connect Guide and Reference, chapter 3, "IMS Connect and IMS Coexistence" for more information about IMS and IMS Connect coexistence.
- Resource Access Control Facility (RACF) or an equivalent product.

**Note:** *This document uses the term RACF when referring to RACF (Resource Access Control Facility) or equivalent products.*

# Installing the IMS eWay

This chapter explains the procedures for installing the IMS eWay.

### Chapter Topics

- [Installing the IMS eWay](#) on page 10
- [Before installing the eWay](#) on page 10
- [After Installation](#) on page 11

---

## 2.1 Installing the IMS eWay

During the eGate Integrator installation process, the Enterprise Manager, a web-based application, is used to select and upload eWays (eWay.sar files) from the eGate installation CD-ROM to the Repository.

When the Repository is running on an HP NonStop Server, or UNIX operating system, eGate and the eWays are installed using the Enterprise Manager on a computer running Windows connected to the Repository server.

### Before installing the eWay

Open and review the **Readme.txt** prior to installation, for any additional information or requirements.

### Installing the IMS eWay on an eGate supported system

The IMS eWay is installed during the installation of the eGate Integrator. The eGate installation process includes the following operations:

- Installing the eGate Repository
- Uploading products to the Repository
- Downloading components (including eGate Enterprise Designer and Logical Host)
- Viewing product information home pages

Follow the instructions for installing the eGate Integrator in the *eGate Integrator Installation Guide*, and include the following steps:

- 1 During the procedures for uploading files to the eGate Repository using the Enterprise Manager, after uploading the **eGate.sar** file, select and upload the following files:
  - ♦ **IMSeWay.sar** (to install the IMS eWay)
  - ♦ **MFS.sar** (to install the MFS Wizard)
  - ♦ **FileeWay.sar** (to install the File eWay, used in the sample project)
  - ♦ **IMSeWayDocs.sar** (to download the IMS eWay user's guide)
- 2 Continue installing the eGate Integrator as instructed in the *eGate Integrator Installation Guide*.

## After Installation

Once the eWay is installed and configured it must then be incorporated into a project before it can perform its intended functions. See the *eGate Integrator User's Guide* for more information on incorporating the eWay into an eGate project.

# Configuring the eWay Properties

This chapter describes how to create and configure the IMS eWay properties.

## Chapter Topics

- [Creating and Configuring the IMS eWay](#) on page 12
- [Using the Properties Sheet](#) on page 13
- [IMS eWay Connectivity Map Properties](#) on page 15
- [IMS eWay Environment Explorer Configuration Parameters](#) on page 16

---

## 3.1 Creating and Configuring the IMS eWay

All eWays contain a set of parameters with properties unique to that eWay type. After the eWays are established and an IMS External System is created in the project's Environment, the eWay parameters can be modified for your specific system. The IMS eWay parameters are modified from two locations:

- From the **Connectivity Map**. These parameters most commonly apply to a specific eWay, and may vary from other eWays (of the same type) in the project.
- From the **Environment Explorer tree**. These parameters are commonly global, applying to all eWays (of the same type) in the project. The saved properties are shared by all eWays in the IMS External System window.

The properties for the IMS eWay must be set in both locations.


### 3.1.1 Selecting IMS as the External Application

To create an IMS eWay, you must first create an IMS External Application in your Connectivity Map. IMS eWays are located between an IMS External Application and a Service. Services are containers for Java Collaborations, Business Processes, eTL processes, and so forth.

#### To create the IMS External Application

- 1 From the Connectivity Map toolbar, click the **External Applications** icon.
- 2 Select the **IMS External Application** from the menu (see [Figure 2 on page 13](#)). The selected IMS External Application tool appears on the Connectivity Map toolbar.


Figure 2 External Applications Selection Menu



- 3 Drag the new **IMS External Application** from the toolbar onto the Connectivity Map canvas. This represents an external IMS system.

From the Connectivity Map, you can associate (bind) the External Application with the Service to establish an eWay (see Figure 3).

Figure 3 eWay Location



When IMS is selected as the External Application, it automatically applies the default IMS eWay properties, provided by the OTD, to the eWay that connects it to the Service. These properties can then be or modified for your specific system using the **Properties Sheet**.

### 3.1.2 Creating Custom Properties for an IMS eWay

A project's eWay properties can be modified after the eWays have been established in the Connectivity Map and the Environment has been created.

#### Modifying the IMS eWay (Connectivity Map) Properties

- 1 From the Connectivity Map, double click the eWay icon, located in the link between the associated External Application and the Service.
- 2 The eWay **Properties Sheet** opens to the eWay IMS Connectivity Map parameters. Make any necessary modifications and click **OK** to save the settings.

#### Modifying the IMS eWay (Environment Explorer) Properties

- 1 From the Environment Explorer tree, right-click the IMS external system. Select **Properties** from the shortcut menu. The **Properties Sheet** appears.
- 2 Make any necessary modifications to the Environment parameters of the IMS eWays, and click **OK** to save the settings.


### 3.1.3. Using the Properties Sheet

Modifications to the eWay configuration properties are made from the IMS eWay Properties Sheet.

### To modify the default eWay configuration properties

- 1 Open the Properties Sheet to the IMS eWay default properties. An eWay has two different sets of parameters: those specific to that particular eWay (accessed from the Connectivity Map), and those that are common to all eWays of this type (accessed from the Environment Explorer tree).
- 2 From the upper-right pane of the Properties Sheet, select a subdirectory of the configuration directory. The parameters contained in that subdirectory are now displayed in the Properties pane of the Properties Sheet. For example, clicking on the **connector** subdirectory displays the editable parameters in the right pane, as shown in Figure 4.

Figure 4 Properties Sheet - IMS eWay parameters



- 3 Click on any property field to make it editable. For example, click on the **class** parameter to edit the class value. If a parameter's value is true/false or multiple choice, the field reveals a submenu of property options.

Click on the ellipsis (. . .) in the properties field to open a separate configuration dialog box. This is helpful for large values that cannot be fully displayed in the parameter's property field. Enter the property value in the dialog box and click **OK**. The value is now displayed in the parameter's property field.

- 4 A description of each parameter is displayed in the **Description** pane when that parameter is selected, providing an explanation of any required settings or options.
- 5 The **Comments** pane provides an area for recording notes and information regarding the currently selected parameter. This is saved for future referral.
- 6 After modifying the configuration properties, click **OK** to close the Properties Sheet and save the changes.

---

## 3.2 IMS eWay Connectivity Map Properties

The IMS eWay configuration parameters, accessed from the Connectivity Map, are organized into the following sections:

- **Connector** on page 15

### 3.2.1. Connector

The Connector section contains the following top level parameters:

- **Class** on page 15
- **Property.Tag** on page 15
- **Type** on page 16

#### Class

##### Description

Specifies the class name of the ETD connector object.

##### Required Values

- String-set. A valid package name. The default is **com.stc.eways.ims.IMSClientETDConnector**.

#### Property.Tag

##### Description

Specifies the identity of the data source. This parameter is required by the current EBobConnectorFactory.

##### Required Values

String-set. A valid data source package name.

## Type

### Description

Specifies the connector type.

### Required Values

String-set. The value is always **IMSClientETD** by default for IMSClientETD connections.

---

## 3.3 IMS eWay Environment Explorer Configuration Parameters

The IMS eWay configuration parameters, accessed from the Environment Explorer tree, are organized into the following sections:

- [TCPIP Configuration](#) on page 16
- [IRM Header](#) on page 17

### 3.3.1. TCPIP Configuration

The TCPIP Configuration section contains information for connecting to Portal Infranet. This section contains the following top level parameters:

- [Port](#) on page 16
- [Server](#) on page 16

#### Port

##### Description

Specifies the port that IMS Connect is listening on. This parameter is mandatory.

##### Required Values

- String-set. The number for the port on which IMS Connect is listening.

#### Server

##### Description

Specifies the name of the server host. This parameter is mandatory.

##### Required Values

String-set. The computer name of the server.



### 3.3.2. IRM Header

The IRM (IMS Request Message) Header section contains the following top level parameters:

- [IRM\\_CLIENTID](#) on page 17
- [IRM\\_DESTID](#) on page 17
- [IRM\\_F1 \(MFS MOD Names\)](#) on page 18
- [IRM\\_F2 \(COMMIT MODE\)](#) on page 18
- [IRM\\_F3 \(Sync Level\)](#) on page 18
- [IRM\\_F4 \(ACK/NAK/ Response\)](#) on page 19
- [IRM\\_F5 \(Flow Control\)](#) on page 19
- [IRM\\_ID](#) on page 20
- [IRM\\_LEN](#) on page 20
- [IRM\\_LTERM](#) on page 20
- [IRM\\_RACF\\_GRNAME](#) on page 20
- [IRM\\_RACF\\_PW](#) on page 21
- [IRM\\_RACF\\_USERID](#) on page 21
- [IRM\\_SOCT](#) on page 21
- [IRM\\_TIMER](#) on page 21
- [IRM\\_TRNCOD](#) on page 22
- [IRM\\_TRNCOD\\_SRC](#) on page 22

**Note:** For a full description of the IRM header, see IBM's *IMS Connect Guide and Reference* (SC27-0946-00).

#### IRM\_CLIENTID

##### Description

Specifies the name of the client ID (character string) that is used by IMS Connect. If this string is not supplied from the client, then the user exit must generate it. The client ID is returned to IMS Connect from the exit in the EXIT PARMLIST field, EXPREA\_CLID.

##### Required Values

String-set. A valid client ID used by IMS Connect. The configured default is STCEWAY.

#### IRM\_DESTID

##### Description

Specifies the Datastore name (IMS destination ID). This field must be specified by the client.

### Required Values

String-set. A valid Datastore name/IMS destination ID (character string).

## IRM\_F1 (MFS MOD Names)

### Description

Specifies whether the MFS Message Output Descriptor (MOD) should be returned as part of the output.

- **MFS**: The user requests MFS MOD name to be returned.
- **NO\_MFS**: The user requests no MFS MOD name to be returned.

When MFS is specified, a Request Mod Message (RMM) is returned as the first structure of the output message. This structure will have an ID of \*REQMOD\* followed by the MFS MOD name. For details, see IBM's IMS Connect Guide and Reference, (SC27-0946-00), page 59.

### Required Values

Select one of the two options. The configured default is NO\_MFS.

## IRM\_F2 (COMMIT MODE)

### Description

Specifies the **Commit Mode**. If this value is not supplied from the client, the user exit must use a default value.

- **COMMIT\_MODE\_0**:
- **COMMIT\_MODE\_1**:

### Required Values

Select one of the two options. The configured default is COMMIT\_MODE\_0.

## IRM\_F3 (Sync Level)

### Description

Specifies the Sync Level. If this value is not supplied from the client, the user exit must use a default value. I

- **SYNC\_LEVEL\_CONFIRM**: Must be used when the IRM\_F2 parameter (commit mode) is set to COMMIT\_MODE\_0.
- **SYNC\_LEVEL\_NONE**:

### Required Values

Select one of the two options. If COMMIT\_MODE\_0 (IRM\_F2) is used, the Sync level must be SYNC\_LEVEL\_CONFIRM. The configured default is SYNC\_LEVEL\_CONFIRM.

## IRM\_F4 (ACK/NAK/ Response)

### Description

Specifies the ACK/NAK/response expression sent to IMS Connect and forwarded to IMS. When the value is received and passed to the user exit, the exit builds the appropriate OTMA structure and returns it to IMS Connect. The ACK/NAK/DEALLOCATE/RESUME [A/N/D/R] must be sent to IMS Connect with no data element.

- **ACK:** Positive acknowledgment, used in response to a message sent to the client where the SYNC level is CONFIRM (SYNC\_LEVEL\_CONFIRM).
- **NACK:** Negative acknowledgment, used in response to a message sent to the client where the SYNC level is CONFIRM (SYNC\_LEVEL\_CONFIRM).
- **DEALLOCATE:** Deallocate connection is used to terminate rather than complete the conversation.
- **RESUME:** Resume TPIPE is used to request Asynchronous output data from IMS. (Not yet implemented)
- **SENDONLY:** Send only, used for a non-response transaction and for sending data to IMS.
- **NO\_ACK:** No request for acknowledgment or deallocation. When a response mode transaction or conversational transaction is being sent to IMS Connect, IRM\_F4 should be set to NO\_ACK.

### Required Values

Select one of the six options. The configured default is NO\_ACK.

## IRM\_F5 (Flow Control)

### Description

Specifies Flow Control properties.

*Note:* SeeBeyond recommends using the default value **No\_Auto\_Flow**. Contact SeeBeyond Support before using any value other than **No\_Auto\_Flow**.

- **Client\_Headers:** OTMA headers are built by the client.
- **Client\_Translation:** Translation is done by the client.
- **Single\_Message:** Only one message is returned on receive following the resume tpipe.
- **No\_Auto\_Flow:** No auto flow of messages (see meaning for No\_Auto\_Flow\_Out).
- **Auto\_Flow\_Out:** Auto flow of messages. All current messages are returned, one at a time, and the last receive waits for the next message for the IRM\_TIMER value. Set the IRM\_TIMER to be a large value. Use only if the client is a dedicated output client.
- **No\_Auto\_Flow\_Out:** No auto flow of messages. All current messages are returned, one at a time, and the last receive waits for the next message for the IRM\_TIMER

value. Set the IRM\_TIMER to be a small value. Use only if the client is a dedicated output client. This value is similar to Auto\_Flow\_Out, as described above, except that the IRM\_TIMER will cause the last receive to terminate.

### Required Values

The recommended setting is No\_Auto\_Flow (default).

## IRM\_ID

### Description

Specifies the identifier (character string) of the user exit that is to be driven after the complete message has been received. The IMS Connect-supplied user message exits reserve and use these IDs:

- \*IRMREQ\* for HWSIMSO0
- \*SAMPLE\* for HWSSMPL0

### Required Values

String-set. One of the three identifier character strings. The configured default is \*SAMPLE\*.

## IRM\_LEN

### Description

Specifies the length of the IRM structure. The minimum size of the IRM for user written exits is 32. HWSIMSO0 and HWSSMPL0 have a minimum IRM length of 80.

### Required Values

String-set. A valid IRM structure length. The configured default is 80.

## IRM\_LTERM

### Description

Specifies the IMS LTERM override. This field can be set to a valid name or to blanks.

### Required Values

String-set. A valid LTERM name or blanks.

## IRM\_RACF\_GRNAME

### Description

Specifies the RACF Group Name. The client must provide the RACF group name if RACF is to be used.

### Required Values

String-set. A valid RACF group name.

## IRM\_RACF\_PW

### Description

Specifies the RACF PASSTICKET. The client must provide the RACF PASSTICKET if RACF is to be used.

### Required Values

String-encrypt. A valid RACF PASSTICKET.

## IRM\_RACF\_USERID

### Description

Specifies the RACF User ID. The client must provide the RACF user ID if RACF is to be used.

### Required Values

String-set. A valid RACF user ID.

## IRM\_SOCT

### Description

Specifies the socket connection type.

- **Transaction:** Transaction socket. The socket connection lasts across a single transaction.
- **Persistent:** Persistent socket. The socket connection lasts across multiple transactions.
- **Non\_Persistent:** Non-persistent socket. The socket connection lasts for a single exchange consisting of one input and one output.

*Note:* This socket type is not recommended when implementing conversational transactions due to the multiple connects and disconnects that would occur as a result.

## IRM\_TIMER

### Description

Specifies the time delay for the receive to the datastore after an ACK.

- **.25 SEC:** .25 seconds.
- **No\_Wait:** Does not set the timer (no wait occurs).
- **Block:** The receive waits indefinitely.

### Required Values

Select one of the three options. The configured default is .25 SEC.

### Required Values

Select one of the three options. The configured default is Transaction.

## IRM\_TRNCOD

### Description

Specifies the default IMS transaction code.

### Required Values

String-set. A valid transaction code.

## IRM\_TRNCOD\_SRC

### Description

Specifies where the transaction code is taken.

- **CFG:** The transaction code is to be taken from the configuration file.
- **MESSAGE:** the transaction code is the first 8 bytes of the message.

### Required Values

Select one of the two options. The configured default is CFG.

# Using the IMS eWay With eInsight

This chapter describes how to use the IMS eWay with ICAN Suite's eInsight Business Process Manager and its engine's Web Services interface.

**Note:** You must have the *eInsight.sar* file installed to use the Web Services interface.

## Chapter Topics

- [eInsight Engine and Components](#) on page 23
- [The IMS eWay With eInsight](#) on page 24
- [IMS eWay eInsight Sample Project](#) on page 24

---

## 4.1 eInsight Engine and Components

eGate components can be deployed as Activities in eInsight business processes. Once a component is associated with an Activity, eInsight invokes it using a Web Services interface. eGate components that can interface with eInsight in this way include the following:

- Object Type Definitions (OTDs)
- eWays
- Collaborations

Using the Enterprise Designer and eInsight, you can add an Activity to a Business Process, then associate that Activity with an eGate component, for example, an eWay. Then, when eInsight runs the Business Process, it automatically invokes that component via its Web Services interface.

See the *eInsight Business Process Manager User's Guide* for details.

---

## 4.2 The IMS eWay With eInsight

An eInsight Business Process Activity can be associated with the IMS eWay during the system design phase. To make this association, select the desired operators under the eWay in the Enterprise Explorer and drag it onto the eInsight Business Process Designer canvas.

The IMS eWay has the following operators available:

- IMSRequest

The operation is automatically changed to an Activity with an icon identifying the component that is the basis for the Activity. At run time, eInsight invokes each step in the order defined in the Business Process. Using eInsight's Web Services interface, the Activity in turn invokes the IMS eWay.

---

## 4.3 IMS eWay Considerations

The following items must be considered when implementing an IMS eWay project:

- The following error message may appear in the mainframe log, even when the IMS eWay runs successfully:

**HWSP1435E Socket closed; Request message incomplete; M=SDRC**

This is an erroneous error message that originates from IBM's IMS Connect program. The error message is resolved by the following PTFs from IBM:

- ♦ PQ53848 (UQ68076) for IMS Connect 1.1
- ♦ PQ62496 (UQ68078) for IMS Connect 1.2.

---

## 4.4 IMS eWay eInsight Sample Project

The following IMS eInsight Business Process sample carries out the same tasks as the IMS\_Collab Collaboration used in IMS\_BP\_Sample sample project.

To create a sample project using a IMS eInsight Business Process, follow the directions for the IMS\_BP\_Sample sample project (see [The IMS\\_JCE\\_Sample Project](#) on page 40), but rather than creating and inserting the Java Collaboration, simply drag and drop the completed Business Process into the Connectivity Map, substituting it for the **IMS\_Collab** Collaboration used in the existing project (see [Creating Collaboration Bindings](#) on page 47). Then complete and run the project as directed



---

## 4.5 Importing a Sample Project

To import a sample eWay project to the Enterprise Designer do the following:

- 1 The sample files are uploaded with the eWay's documentation .sar file and downloaded from the Enterprise Manager's Documentation tab. Extract the samples from the Enterprise Manager to a local file.
- 2 Save all unsaved work before importing a sample project.
- 3 From the Enterprise Designer's Project Explorer pane, right-click the Repository and select **Import** from the shortcut menu. The **Import Manager** appears.
- 4 Browse to the directory that contains the sample project zip file. Select the sample file (for this sample, **IMS\_BP\_Sample.zip**) and click **Import**. After the sample project is successfully imported, click **Close**.
- 5 Before an imported sample project can be run you must do the following:
  - ♦ Create an **Environment** (see [Creating an Environment](#) on page 32)
  - ♦ Configure the eWays properties for your specific system (see [Configuring the eWays](#) on page 33)
  - ♦ Create a **Deployment Profile** (see [Creating and Activating the Deployment Profile](#) on page 35)

The following pages provide step by step directions for manually creating the IMS\_BP\_Sample project.

---

## 4.6 The IMS\_BP\_Sample Project

The **IMS\_BP\_Sample** project demonstrates connectivity with an external IMS system.

### Sample Project Overview

- 1 The inbound File eWay receives a file from an external directory.
- 2 This file is the published by the IMS eWay to an external IMS application.
- 3 The IMS eWay receives the file back from the external IMS application, and publishes the file to the outbound File eWay.


The outbound File eWay publishes the file to an external directory.

### 4.6.1. Creating a Project

The first step is to create a new project in the SeeBeyond Enterprise Designer.

- 1 Start the Enterprise Designer.
- 2 From the Enterprise Explorer's Project Explorer tab, right-click the Repository and select **New Project** (see Figure 5). A new project (Project1) appears on the Project Explorer tree.

**Figure 5** Enterprise Explorer - New Project



- 3 Click twice on **Project1** and rename the project (for this sample, **IMS\_BP\_Sample**).


## 4.6.2 Creating a Business Process

To create the IMS eInsight Business Process, do the following:

### Creating the Business Process Flow

- 1 Right-click an existing project (for this sample **IMS\_BP\_Sample**) in the Enterprise Designer's Project Explorer, and select **New > Business Process** from the shortcut menu. The eInsight Business Process Designer appears and **IMS\_BP** is added to the Project Explorer tree.
- 2 From the Project Explorer tree, expand the SeeBeyond > eWays > IMSeWay > IMS\_eWay, and File > FileClient nodes.
- 3 Populate the eInsight Business Process Designer's modeling canvas with the following activities from the Project Explorer tree, as displayed in Figure 6:
  - ♦ **receive**, under SeeBeyond > eWays > File > FileClient
  - ♦ **IMSRequest**, under SeeBeyond > eWays > IMSeWay > IMS\_eWay
  - ♦ **write**, under SeeBeyond > eWays > File > FileClient


**Figure 6** eInsight Business Process Designer - Populate the Canvas



4 Link the modeling elements by clicking on the element's connector and dragging the cursor to the next element's connector, making the following links as displayed in Figure 7.

- ◆ Start -> FileClient.receive
- ◆ FileClient.receive -> IMS\_eWay.IMSRequest
- ◆ IMS\_eWay.IMSRequest ->FileClient.write
- ◆ FileClient.write -> End

**Figure 7** eInsight Business Process Designer - Link the Modeling Elements




## Configuring the Modeling Elements

Business Rules, created between the Business Process Activities, allow you to configure the relationships between the input and output Attributes of the Activities using the Business Process Editor's Business Rules Designer.

### Adding Business Rules

- 1 Right-click the link between the **FileClient.receive** and **IMS\_eWay.execute** Activities and select **Add Business Rule** from the shortcut menu.
- 2 Repeat step 1 for the link between **IMS\_eWay.execute** and **JMS.send** (see Figure 8).


**Figure 8** eInsight Business Process Designer - Adding Business Rules



### Using the Business Rules Designer


- 1 From the eInsight Business Process Designer toolbar, click the **Map Business Process Attributes** button. The Business Rules Designer appears at the bottom of the eInsight Business Process Designer.
- 2 Click on the **Business Rule** icon in the link between **FileClient.receive** and **IMS\_eWay. IMSRequest** to display the Business Rule Input and Output Attributes in the Business Rules Designer. These Attributes can now be modified.
- 3 Map from **text**, under FileClient.receive.Output in the Output pane, to **message** under IMS eWay. IMSRequest.Input > input in the Input pane. This is done by clicking on **text** and dragging the cursor to **message** (see Figure 9).

**Figure 9** eInsight Business Rules Designer



- 4 From the Enterprise Explorer, right-click the Repository and select **Save Changes into Repository** from the shortcut menu, to save your current changes.
- 5 To configure the second Business Rule, click on the Business Rule in the link between the **IMS\_eWay.IMSRequest** and **FileClient.write** Activities. This Business Rule is now displayed in the Business Rules Designer.
- 6 Map **reply**, under **IMS\_eWay.IMSRequest.Output** > **output** in the Output pane of the Business Rules Designer, to **text**, under **FileClient.write.Input** in the Input pane as displayed in **Figure 10 on page 29**.

**Figure 10** eInsight Business Rules Designer



- 7 When the Business Process is complete, from the eInsight Business Process Designer toolbar, click the **Synchronize Graphical Model and Business Process** icon to synchronize the graphical interface to the Business Process code.
- 8 Save your current changes to the Repository.

### 4.6.3 Creating a Connectivity Map

The Connectivity Map provides a canvas for assembling and configuring a project's components.


- 1 From the Project Explorer tree, right-click the new **IMS\_BP\_Sample** project and select **New > Connectivity Map** from the shortcut menu.
- 2 The New Connectivity Map appears and a node for the Connectivity Map is added under the project on the Project Explorer tree labeled **CMap1**. Rename the Connectivity Map **IMS\_BP\_Sample\_CM**.

The icons in the toolbar represent the available components used to populate the Connectivity Map canvas.

### Selecting the External Applications

In the Connectivity Map, the eWays are associated with External Systems. For example, to establish a connection to IMS, you must first select IMS as an External System to use in your Connectivity Map (see **Figure 11 on page 30**).

**Figure 11** Connectivity Map - External Applications




- 1 Click the **External Application** icon on the Connectivity Map toolbar,
- 2 Select the external systems needed for your project (for this sample, **IMS** and **File**). Icons representing the selected external systems are added to the Connectivity Map toolbar.

## Populating the Connectivity Map

Add the project components to the Connectivity Map by dragging the icons from the toolbar to the canvas.

- 1 For this sample, drag the following components onto the Connectivity Map canvas as displayed in Figure 12:
  - ♦ **File External System (2)**
  - ♦ **Service** (A service is a container for Java Collaborations, Business Processes, eTL processes, and so forth) This can also be created by dragging the Business Process over from the Project Explorer tree.
  - ♦ **IMS External System**

**Figure 12** Connectivity Map with Components




- 2 Rename the Connectivity Map objects by right-clicking the object's name, selecting **Rename** from the shortcut menu, and typing the new name. Rename the objects as follows:
  - ♦ **File1** to **FileIn**
  - ♦ **Service1** to **IMSBP**
  - ♦ **File2** to **FileOut**
- 3 Save your current changes to the Repository.

## 4.6.4. Binding the eWay Components

After the Business Processes have been written, the components are associated and bindings are created in the Connectivity Map.


- 1 From the Project Explorer, double-click the Connectivity Map **IMS\_BP\_Sample\_CM**. The Enterprise Designer canvas now displays the Connectivity Map.
- 2 Drag and drop the **IMS\_BP** Business Process from the Project Explorer onto the Service (**IMSBP**). If the Business Process was successfully associated, the Service's icon changes to a Business Process icon (see Figure 13).

**Figure 13** Connectivity Map - Binding the eWay Components



- 3 Double-click **IMSBP**. The **IMSBP Binding dialog box** appears using the **IMS\_BP Rule**.
- 4 From the **IMSBP** Binding dialog box, drag **FileSender** (under Implemented Services) to the **FileIn** (File) External Application.
- 5 From the **IMSBP** Binding dialog box, drag **IMS\_Receiver** (under Invoked Services) to the **IMS1** External Application.
- 6 From the **IMSBP** Binding dialog box, drag **FileReceiver** to the **FileOut** External Application (see [Figure 14 on page 32](#)). Minimize the **IMSBP** Binding dialog box by clicking the chevrons in the upper-right corner.

**Figure 14** Connectivity Map - Associating (Binding) the Project's Components



- 7 Save your current changes to the Repository.

### 4.6.5. Creating an Environment


Environments include the external systems, Logical Hosts, integration servers, and JMS IQ Managers used by a project, and contain the configuration information for these components. Environments are created using the Enterprise Designer's Environment Explorer and Environment Editor.

- 1 From the Enterprise Designer's Enterprise Explorer, click the **Environment Explorer** tab.
- 2 Right-click the Repository and select **New Environment**. A new Environment is added to the Environment Explorer tree.
- 3 Rename the new Environment to **IMS\_BP\_Sample\_ENV**.
- 4 Right-click **IMS\_BP\_Sample\_ENV** and select **New IMS External System**. Name the External System **IMSExtSys**. Click **OK**. **IMSExtSys** is added to the Environment Editor.
- 5 Right-click **IMS\_BP\_Sample\_ENV** and select **New File External System**. Name the External System **FileExtSysIn** and select **Inbound File eWay** as the **External System Type**. Click **OK**. **FileExtSysIn** is added to the Environment Editor.
- 6 Right-click **IMS\_BP\_Sample\_ENV** and select **New File External System**. Name this External System **FileExtSysOut** and select **Outbound File eWay** as the **External System Type**. **FileExtSysOut** is added to the Environment Editor.
- 7 Right-click **IMS\_BP\_Sample\_ENV** and select **New Logical Host**. The **LogicalHost1** box is added to the Environment and **LogicalHost1** is added to the Environment Editor tree.
- 8 From the Environment Explorer tree, right-click **LogicalHost1** and select **New SeeBeyond Integration Server**. A new Integration Server (**IntegrationSvr1**) is added to the Environment Explorer tree under **LogicalHost1**.




- 9 Save changes to the repository. The Environment Explorer and Environment Editor now appear as displayed in **Figure 15 on page 33**.

**Figure 15** Environment Editor



#### 4.6.6. Configuring the eWays

The IMS\_BP\_Sample project uses three eWays, each represented in the Connectivity Map as a node between an External Application and a Business Process (see Figure 16). eWays facilitate communication and movement of data between the external applications and the eGate system.



The File eWay properties are configured from the Connectivity Map. The IMS eWay properties are set from both the Project Explorer's Connectivity Map and the Environment Explorer. To configure the eWays do the following:

#### Configuring the File eWays

- 1 Double-click the inbound **File eWay**, select **Inbound File eWay** in the Templates dialog box and click **OK**.
- 2 The **Properties Sheet** opens to the inbound File eWay properties. Modify the properties for your system, including the settings for the inbound File eWay in Table 1, and click **OK**.

**Table 1** Inbound File eWay Settings

Inbound eWay Connection Parameters	
Directory	C:/temp
Input file name	Input*.txt

- 3 In the same way, modify the outbound File eWay configuration for your system, including the settings in Table 2, and click **OK**.

**Table 2** Outbound File eWay Settings

Outbound eWay Connection Parameters	
Directory	C:/temp
Output file name	output%.dat

## Configuring the IMS eWay

The IMS eWay properties must be set in both the Project Explorer and Environment Explorer. For more information on the IMS eWay properties and the Properties Sheet, see [Configuring the eWay Properties](#) on page 12 or see the *eGate Integrator User's Guide*.

For the IMS\_BP\_Sample project, do the following:

### Modifying the IMS eWay Connectivity Map Properties

- 1 From the **Connectivity Map**, double-click the **IMS eWay**. The **Properties Sheet** opens to the IMS eWay project configuration properties.
- 2 Modify the IMS eWay (Project Explorer) configuration for your system, including the settings in [Table 3 on page 34](#), and click **OK**.

**Table 3** IMS Project Explorer eWay Settings

IMS eWay Connectivity Map Properties	
<b>Connector</b> Set as directed, otherwise use the default settings	
Class	com.stc.eways.IMS.IMSClientConnector
Property.Tag	The data source
Type	IMSClientETD

### Modifying the IMS eWay Environment Explorer Properties

- 1 From the **Environment Explorer** tree, right-click the IMS External System (**IMSExtSys** in this sample), and select **Properties** from the shortcut menu. The **Properties Sheet** opens to the IMS eWay Environment Explorer properties.
- 2 Modify the IMS eWay Environment Explorer properties for your system, including the settings in Table 4, and click **OK**.

**Table 4** IMS Environment Explorer eWay Settings

<b>IMS eWay Environment Explorer Properties</b>	
<b>TCPIP Configuration</b> Set as directed, otherwise use the default settings	
Port	7777
Server	Server host name
<b>IRM Header</b> Set as directed, otherwise use the default settings.	
IRM_CLIENTID	The name of the client ID that is used by IMS Connect
IRM_DESTID	The Datastore name
IRM_RACF_GRNAME	The RACF group name - if RACF is to be used
IRM_RACF_PW	The RACF PASSTICKET - if RACF is to be used
IRM_RACF_USERRID	The RACF user ID - if RACF is to be used


#### 4.6.7 Creating and Activating the Deployment Profile

A Deployment Profile is used to assign Collaborations and message destinations to the integration server and JMS IQ Manager. Deployment profiles are created using the Deployment Editor.

To create the IMS\_BP\_Sample Deployment Profile do the following:

- 1 From the Enterprise Explorer's Project Explorer, right-click the project (**IMS\_BP\_Sample**) and select **New > Deployment Profile** from the shortcut menu.
- 2 Enter a name for the Deployment Profile (for this sample **IMS\_BP\_Sample\_DP**). Make sure that the selected Environment is **IMS\_BP\_Sample\_ENV**. Click **OK**. The Deployment Profile Editor appears.
- 3 From the left pane of the Deployment Editor, drag the **FileIn -> IMSBP** (external application) object to the **FileExtSysIn** window.
- 4 Drag the **IMSBP -> FileOut** (external application) object to the **FileExtSysOut** window.
- 5 Drag the **IMSBP -> IMS1** (external application) to the **IMSExtSys** window.
- 6 Drag the **IMSBP** Business Process to **IntegrationSvr1** in the **LogicalHost1** window (see Figure 17).

**Figure 17** Deployment Profile



- 7 Click **Activate**. When activation succeeds, save the changes to the Repository.

#### 4.6.8. Running the Project

The following directions assume that the Enterprise Designer was downloaded to C:\ican50. If this is not the case, replace that location in the following directions with the appropriate location. A new LogicalHost must be downloaded for each project.

- 1 From the Enterprise Manager Downloads tab, double-click **Logical Host - for win32**.
- 2 Extract the file to the C:\ican50\LogicalHost1 directory. You must specify the **LogicalHost1** directory for it to be created.
- 3 Navigate to the C:\ican50\LogicalHost1\logicalhost\bootstrap\config directory and open the logical-host.properties file using Notepad™.
- 4 Enter and save the following information in the appropriate fields:
  - ♦ Logical Host root directory: C:\ican50\LogicalHost1
  - ♦ Repository URL: **http://localhost:port number/repository name**
  - ♦ Repository user name and password: *Your user name and password*
  - ♦ Logical Host Environment name: **IMS\_BP\_Sample\_Env**
  - ♦ Logical Host name: **LocalHost**

Save your changes to **logical-host.properties** and close the file.

- 5 Run the **bootstrap.bat** file located in the C:\ican50\LogicalHost1\logicalhost\bootstrap\bin directory.
- 6 Copy the sample input data file to the input directory.

---

## 4.7 Alerting and Logging

eGate provides an alerting and logging feature. This allows monitoring of messages, and captures any adverse messages in order of severity based on configured severity level and higher. To enable Logging, please see the *eGate Integrator User's Guide*.

**Note:** *The alerts/status notifications for the IMS eWay are currently limited to Started, Running, Stopping, and Stopped.*

# Implementing an IMS eWay Project

This chapter provides an introduction to the IMS eWay components and information on how these components are created and implemented in an eGate project. It is assumed that the reader understands the basics of creating a project using the SeeBeyond Enterprise Designer. For more information on creating an eGate project see the *eGate Tutorial* and the *eGate Integrator User's Guide*.

## Chapter Topics

- [IMS eWay Components](#) on page 38
- [Importing a Sample Project](#) on page 39
- [The IMS\\_JCE\\_Sample Project](#) on page 40
- [The IMS\\_MFS\\_Sample Project](#) on page 54
- [The MFS\\_IMS\\_Sample Project](#) on page 63

---

## 5.1 IMS eWay Components

This chapter presents a sample IMS eWay project created using the same procedures as the sample end-to-end project provided in the *eGate Integrator Tutorial*. The eWay components that are unique to the IMS eWay include the following:

### IMS eWay Configuration File

The properties file for the IMS eWay contains the parameters that are used to connecting with a specific external system. These parameters are set using the Properties Sheet. For more information about the IMS eWay properties File and the Properties Sheet see [Creating and Configuring the IMS eWay](#) on page 12.

### IMSClientETD OTD

The IMSClientETD OTD is provided with the eWay and contains methods and attributes that are used to create the Business Rules that invoke the IMS program. The nodes of the OTD take their initial value from the eWay Connection configuration parameters, but can be changed in the Collaboration.

### IMS MFS Wizard

The IMS MFS Wizard builds an Object Type Definition from an IMS message format service (MFS) file. The wizard generates Object Type Definitions (OTDs) that map input and output message segments at the field level.

---

## 5.2 IMS eWay Considerations

The following items must be considered when implementing an IMS eWay project:

- The following error message may appear in the mainframe log, even when the IMS eWay runs successfully:

**HWSP1435E Socket closed; Request message incomplete; M=SDRC**

This is an erroneous error message that originates from IBM's IMS Connect program. The error message is resolved by the following PTFs from IBM:

- ♦ PQ53848 (UQ68076) for IMS Connect 1.1
- ♦ PQ62496 (UQ68078) for IMS Connect 1.2.

---

## 5.3 IMS eWay Sample Projects

Two sample projects are provided in the following section that demonstrate how the eWay components are created and implemented in a production environment.

- [The IMS\\_JCE\\_Sample Project](#) on page 40, demonstrates connectivity with an IMS system.
- [The IMS\\_MFS\\_Sample Project](#) on page 54, demonstrates the IMS MFS Builder.
- [The MFS\\_IMS\\_Sample Project](#) on page 63, demonstrates the use of the MFS OTD to compose IVTNO transaction messages.

---

## 5.4 Importing a Sample Project

Sample eWay projects are included as part of the installation CD-ROM package. To import a sample eWay project to the Enterprise Designer do the following:

- 1 The sample files are uploaded with the eWay's documentation .sar file and downloaded from the Enterprise Manager's Documentation tab. Extract the samples from the Enterprise Manager to a local file.
- 2 Save all unsaved work before importing a sample project.
- 3 From the Enterprise Designer's Project Explorer pane, right-click the Repository and select **Import** from the shortcut menu. The **Import Manager** appears.
- 4 Browse to the directory that contains the sample project zip file. Select the sample file (for this sample, **IMS\_JCE\_Sample.zip**) and click **Import**. After the sample project is successfully imported, click **Close**.
- 5 Before an imported sample project can be run you must do the following:
  - ♦ Create an **Environment** (see [Creating an Environment](#) on page 49)

- ◆ Configure the eWays for your specific system (see [Configure the eWays](#) on page 50)
- ◆ Create a **Deployment Profile** (see [Creating and Activating the Deployment Profile](#) on page 52)

---

## 5.5 The IMS\_JCE\_Sample Project

The **IMS\_JCE\_Sample** project demonstrates connectivity with an external IMS system.

### Sample Project Overview


- 1 The inbound File eWay receives a file from an external directory.
- 2 This file is then published by the IMS eWay to an external IMS application.
- 3 The IMS eWay receives the file back from the external IMS application, and publishes the file to the outbound File eWay.
- 4 The outbound File eWay publishes the file to an external directory.

### 5.5.1. Create a Project

The first step is to create a new project in the eGate Enterprise Designer.

- 1 Start the Enterprise Designer.
- 2 From the Enterprise Explorer's Project Explorer tab, select your Repository on the Project Explorer tree, right-click the Repository and select **New Project** (see Figure 18). A new project (Project1) appears on the Project Explorer tree.

**Figure 18** Enterprise Explorer - New Project



- 3 Click twice (not double-click) on **Project1** and rename the project (for this sample, **IMS\_JCE\_Sample**).



## 5.5.2 Create a Connectivity Map

The Connectivity Map provides a canvas for assembling and configuring a project's components.


- 1 In Enterprise Explorer's Project Explorer, right-click the new project and select **New > New Connectivity Map** from the shortcut menu.
- 2 The New Connectivity Map appears and a node for the Connectivity Map is added to the Project Explorer tree labeled **CMap1**. Rename the Connectivity Map **IMS\_JCE\_Sample\_CM**.

### Select the External Applications

The icons on the Connectivity Map toolbar represent the available components used to populate the Connectivity Map canvas.

When creating a Connectivity Map, the eWays are associated with external systems. For example, to establish a connection to IMS, you must first select IMS as an External Application to use in your Connectivity Map (see Figure 19). The IMS External Application icon is then added to the Connectivity Map toolbar.

**Figure 19** Connectivity Map - External Applications



To add the External Applications used with the IMS\_JCE\_Sample project, do the following:


- 1 Click the **External Application** icon on the Connectivity Map toolbar.
- 2 Select the external systems that are necessary for your project (for this sample, **IMS** and **File**). Icons representing the selected external systems are added to the Connectivity Map toolbar.

### Populate the Connectivity Map

Add the project components to the Connectivity Map by dragging the icons from the toolbar to the canvas.

- 1 For this sample, drag the following components onto the Connectivity Map canvas as displayed in [Figure 20 on page 42](#):
  - ♦ File External System (2)
  - ♦ Service (A Service is a container for Java Collaborations, Business Processes, eTL processes, and so forth.)
  - ♦ IMS External System

**Figure 20** Connectivity Map with Components



- 2 Rename the objects by right-clicking the object, selecting **Rename** from the shortcut menu, and typing in the new name. Change the names as follows:
  - ♦ **File1** to **FileIn**
  - ♦ **Service1** to **IMS\_Service**
  - ♦ **File2** to **FileOut**
  - ♦ **IMS1** to **IMS**
- 3 Save your current changes to the Repository.

### 5.5.3. Creating the Collaboration Definitions

The next step in the sample is to create one Collaboration using the Collaboration Definition Wizard (Java). Once a Collaboration Definition has been created, the Business Rules of the Collaboration can be written using the Collaboration Editor (Java).


#### The IMS\_Collab Collaboration (Java)

The IMS\_Collab Collaboration defines transactions from the inbound File eWay to the IMS eWay and from the IMS application to the outbound File eWay.

- 1 From the Project Explorer, right-click the **IMS\_JCE\_Sample** project and select **New > Collaboration Definition (Java)** from the shortcut menu. The **Collaboration Definition Wizard (Java)** appears.
- 2 Enter a Collaboration Definition name (for this sample, **IMS\_Java\_Collab**) and click Next.
- 3 For Step 2 of the wizard, **Select a Web Services Operation**, Double-click **SeeBeyond > eWays > File > FileClient > receive**. The File Name field now displays **receive**. Click Next.

- 4 For Step 3 of the wizard, from the Select OTDs selection window, double-click **SeeBeyond > eWays > IMSeWay > IMS**. The **IMS** OTD is added to the Selected OTDs field.
- 5 Click the **Up One Level** button to return to the Repository. Double-click **SeeBeyond > eWays > File > FileClient**. The **FileClient** OTD is added to the Selected OTDs field (see Figure 21).

**Figure 21** Collaboration Definition Wizard (Java) - Select OTDs



- 6 Click **Finish**. The Collaboration Editor (Java) appears in the left pane of the Enterprise Designer and the **IMS\_Java\_Collab** is added to the Project Explorer tree.


### 5.5.4. Using the Collaboration Editor (Java)

The next step in the sample is to create the Business Rules of the Collaborations using the Collaboration Editor.

### Creating the IMS\_Java\_Collab Collaboration


Be careful to open all nodes specified in the directions to connect to the correct item. The **IMS\_Java\_Collab** Collaboration contains the Business Rule displayed in Figure 22.

Figure 22 IMS\_Java\_Collab Collaboration Business Rules




- A To create the **IMS\_Java\_Collab** Collaboration Business Rules do the following:
- A From the Project Explorer tree, double-click **IMS\_Java\_Collab** to open the Collaboration Editor to the IMS\_Java\_Collab Collaboration.
- 7 To create the **Copy Text to Message** Business Rule do the following:
  - A Map **Text**, under **input** in the left pane of the Business Rules Designer, to **Message**, under **IMS\_1** in the right pane of the Collaboration Editor. To do this, click on **Text**, under **input** in the left pane of the Business Rules Designer, and drag the cursor to **Message**, under **IMS\_1** in the right pane of the Collaboration Editor.
  - B An arrow appears from **Text** to **Message** in the Business Rules Designer pane and **Copy Text to Message** appears as a Business Rule in the Business Rules pane (see Figure 23).

**Figure 23** Copy Text to Message Business Rule




- 8 To create the **IMS\_1.connect** Business Rule do the following:
  - A From the Business Rules toolbar click the **rule** button to add a new rule.
  - B Right-click the **IMS\_1** node in the left pane of the Business Rules Designer, and select **Select a method to call** from the shortcut menu. The method selection box appears.
  - C Select **connect()** from the method selection box. The **connect** method box appears in the Business Rules Designer canvas (see Figure 24).

**Figure 24** IMS\_1.connect Business Rule



- 9 To create the **IMS\_1.IMSRequest** Business Rule do the following:
  - A From the Business Rules toolbar click the **rule** button to add a new rule.
  - B Right-click the **IMS\_1** node in the left pane of the Business Rules Designer, and select **Select a method to call** from the shortcut menu. The method selection box appears.
  - C Select **IMSRequest()** from the method selection box. The **IMSRequest** method box appears in the Business Rules Designer canvas.
- 10 To create the **Copy Reply to Text** Business Rule do the following:
  - A From the Business Rules toolbar click the **rule** button to add a new rule.
  - B Map **Reply**, under **IMS\_1** in the left pane of the Business Rules Designer, to **Text**, under **FileClient\_1** in the right pane of the Collaboration Editor.
- 11 To create the **IMS\_1.disconnect** Business Rule do the following:
  - A From the Business Rules toolbar click the **rule** button to add a new rule.
  - B Right-click **IMS\_1** in the left pane of the Business Rules Designer, and select **Select a method to call** from the shortcut menu. The method selection box appears.
  - C Select **disconnect()** from the method selection box. The **disconnect** method box appears in the Business Rules Designer canvas.
- 12 To create the **FileClient\_1.write** Business Rule do the following:
  - A From the Business Rules toolbar click the **rule** button to add a new rule.
  - B Right-click the **FileClient\_1** node in the left pane of the Business Rules Designer, and select **Select a method to call** from the shortcut menu. The method selection box appears.
  - C Select **write()** from the method selection menu. The **write** method box appears in the Business Rules Designer canvas (see Figure 25).

Figure 25 FileClient\_1.write Business Rule




- 13 Save your current changes to the Repository.

### 5.5.5. Creating Collaboration Bindings

After the Collaboration has been written, the components are associated and Bindings are created in the Connectivity Map.


- 1 From the Project Explorer tree, double-click **IMS\_JCE\_Sample\_CM** to display the Connectivity Map.
- 2 Drag and drop the **IMS\_Java\_Collab** Collaboration from the Project Explorer tree to the **IMS\_Service**. If the Collaboration is successfully associated, the Service icon's "gears" change from red to green (see Figure 26).

**Figure 26** Connectivity Map - Binding the Collaborations



- 3 Double-click **IMS\_Service** in the Connectivity Map. The **IMS\_Service** Binding dialog box appears.
- 4 From the **IMS\_Service** Binding dialog box, map **FileClient input** (under Implemented Services) to the **FileIn** External Application, by clicking on **input** and dragging the cursor to the **FileIn** application.
- 5 From the **IMS\_Service** Binding dialog box, map **IMS IMS\_1** (under Invoked Services) to the **IMS** External Application.
- 6 From the **IMS\_Service** Binding dialog box, map **FileClient\_1 FileClient\_1** to the **File2** External Application (see [Figure 27 on page 48](#)).

**Figure 27** Connectivity Map - Connecting the Project's Components



- 7 Minimize the **IMS\_Service** Binding dialog box, and save your current changes to the Repository.




## 5.5.6. Creating an Environment

Environments include the external systems, Logical Hosts, integration servers and message servers used by a project and contain the configuration information for these components. Environments are created using the Enterprise Designer's Environment Explorer and Environment Editor.

- 1 From the Enterprise Designer's Enterprise Explorer, click the **Environment Explorer** tab.
- 2 Right-click the Repository and select **New Environment**. A new Environment is added to the Environment Explorer tree.
- 3 Rename the new Environment to **IMS\_JCE\_Sample\_Env**.
- 4 Right-click **IMS\_JCE\_Sample\_Env** and select **New IMS External System**. Name the External System **IMSExtSys**. **IMSExtSys** is added to the Environment Editor.
- 5 Right-click **IMS\_JCE\_Sample\_Env** and select **New File External System**. From the **Create an External System** dialog box, enter **FileExtSysIn** as the name and select **Inbound File eWay** as the type. Click **OK**. **FileExtSysIn** is added to the Environment Editor.
- 6 Right-click **IMS\_JCE\_Sample\_Env** and select **New File External System** again. Enter **FileExtSysOut** as the name and select **Outbound File eWay** as the type. **FileExtSysOut** is added to the Environment Editor.
- 7 Right-click **IMS\_JCE\_Sample\_Env** and select **New Logical Host**. The **LogicalHost1 box** is added to the Environment and **LogicalHost1** is added to the Environment Editor tree.
- 8 From the Environment Explorer tree, right-click **LogicalHost1** and select **New SeeBeyond Integration Server** from the shortcut menu. A new Integration Server (**IntegrationSvr1**) is added to the Environment Explorer tree under **LogicalHost1** (see [Figure 28 on page 49](#)).


**Figure 28** Environment Editor



- 9 Save your current changes to the Repository.

### 5.5.7. Configure the eWays

The IMS\_JCE\_Sample project uses three eWays, each represented in the Connectivity Map as a node between an External Application and the Collaboration (see Figure 29). eWays facilitate communication and movement of data between the External Applications and the eGate system.



#### Configuring the File eWays

- 1 Double-click the **inbound File eWay** (see Figure 29). The Templates dialog box appears. Select **Inbound File eWay** in the Templates dialog box and click **OK**.
- 2 The Properties Sheet opens to the inbound File eWay properties. Modify the properties for your system, including the settings in Table 5, and click **OK**. The properties settings are saved for the eWay.

**Table 5** Inbound File eWay Settings

Inbound eWay Configuration Parameters	
Directory	C:/temp
Input file name	Input*.txt

- 3 Double-click the **outbound File eWay** located between **IMS\_Service** and the outbound **File2** External Application, and select **Outbound File eWay**. Modify the outbound File eWay configuration for your system, including the settings in Table 6, and click **OK**.

**Table 6** Outbound File eWay Settings

Outbound eWay Configuration Parameters	
Directory	C:/temp
Output file name	output%.dat

#### Configuring the IMS eWay

The IMS eWay properties must be set in both the Project Explorer and Environment Explorer. For more information on the IMS eWay configuration properties and the Properties Sheet, see [Creating and Configuring the IMS eWay](#) on page 12, or see the *eGate Integrator User's Guide*.

### Modifying the IMS eWay Connectivity Map Properties

- 1 From the **IMS\_JCE\_Sample\_CM** Connectivity Map, double-click the **IMS** eWay. The Properties Sheet opens to the IMS eWay Project Explorer configuration properties.
- 2 Modify the **IMS** eWay (Project Explorer) properties for your system, including the settings in Table 7, and click **OK**.
- 3 Double-click the **IMS eWay** located between **IMS\_Service** and the **IMS1** External Application. Modify the IMS eWay configuration for your system, including the settings in Table 7, and click **OK**.

**Table 7** IMS eWay Project Explorer Configuration Settings

IMS eWay (Project Explorer) Configuration Parameters	
<b>Connector</b> Set as directed, otherwise use the default settings	
class	com.stc.eways.ims.IMSClientETDConnector
type	IMSClientETD

### Modifying the IMS eWay Environment Explorer Properties

- 1 From the **Environment Explorer** tree, right-click the IMS External System (**IMSExtSys** in this sample), and select **Properties**. The Properties Sheet opens to the IMS eWay environment-configuration properties.
- 2 Modify the IMS eWay environment-configuration for your system, including the settings in Table 8, and click **OK**.

**Table 8** IMS eWay Environment Explorer Configuration Settings

IMS eWay (Environment Explorer) Configuration Parameters	
<b>TCPIP Configuration</b> Set as directed, otherwise use the default settings	
Port	7777
Server	Server name
<b>IRM Header Settings</b> Set as directed, otherwise use the default settings.	
IRM_RACF_GRNAME	The RACF group name - if RACF is to be used
IRM_RACF_PW	The RACF PASSTICKET - if RACF is to be used
IRM_RACF_USERRID	The RACF user ID - if RACF is to be used


## 5.5.8 Creating and Activating the Deployment Profile

Deployment Profiles are specific instances of a project in a particular Environment. A Deployment Profile is created using the Enterprise Designer's Deployment Editor.

To create the IMS\_JCE\_Sample\_DP Deployment Profile do the following:

- 1 From the Enterprise Explorer's Project Explorer, right-click the project (IMS\_JCE\_Sample) and select **New > Deployment Profile**.
- 2 From the **Create Deployment Profile for IMS\_JCE\_Sample** dialog box, enter a name for the Deployment Profile (for this sample **IMS\_JCE\_Sample\_DP**), and select **IMS\_JCE\_Sample\_Env** as the Environment. Click **OK**.
- 3 From the left pane of the Deployment Editor, drag **IMS\_Service -> IMS** to the **IMSExtSys** window.
- 4 From the left pane of the Deployment Editor, drag **FileIn -> IMS\_Service** to the **FileExtSysIn** window.
- 5 From the left pane of the Deployment Editor, drag **IMS\_Service -> FileOut** to the **FileExtSysOut** window.
- 6 Drag **IMS\_Service** to **IntegrationSvr1** in the **LogicalHost1** window (see [Figure 30 on page 52](#)).

**Figure 30** Deployment Profile



- 7 Click **Activate**, then save the changes to the Repository.

### 5.5.9. Running the Project

The following directions assume that the Enterprise Designer was downloaded to C:\ican50. If this is not the case, replace that location in the following directions with the appropriate location. A new LogicalHost must be downloaded for each project.

- 1 From the Enterprise Manager Downloads tab, double-click **Logical Host - for win32**.
- 2 Extract the file to the C:\ican50\LogicalHost2 directory. You must specify the **LogicalHost2** directory for it to be created.
- 3 Navigate to the C:\ican50\LogicalHost2\logicalhost\bootstrap\config directory and open the logical-host.properties file using Notepad™.
- 4 Enter and save the following information in the appropriate fields:
  - ♦ Logical Host root directory: C:\ican50\LogicalHost2
  - ♦ Repository URL: **http://localhost;port number/repository name**
  - ♦ Repository user name and password: *Your user name and password*
  - ♦ Logical Host Environment name: **IMS\_JCE\_Sample\_Env**
  - ♦ Logical Host name: **Localhost**

Save your changes to **logical-host.properties** and close the file.

- 5 Run the **bootstrap.bat** file located in the C:\ican50\LogicalHost2\logicalhost\bootstrap\bin directory.
- 6 Copy the sample input data file to the input directory.

### 5.5.10 Alerting and Logging

eGate provides an alerting and logging feature. This allows monitoring of messages, and captures any adverse messages in order of severity based on configured severity level and higher. To enable Logging, please see the *eGate Integrator User's Guide*.

**Note:** *The alerts/status notifications for the IMS eWay are currently limited to Started, Running, Stopping, and Stopped.*

---

## 5.6 The IMS\_MFS\_Sample Project

The IMS\_MFS\_Sample project demonstrates the use of the IMS MFS builder to create an OTD from an MFS file and use it in a simple project.

- 1 Input data, formatted as content to an MFS message output control block, is subscribed to by the inbound File eWay from an external directory.
- 2 This data (message) is deserialized into an OTD generated from an MFS message specification.
- 3 The Collaboration demonstrates field-level data access to the message, concatenates and spools specific field values. The output produced by the Collaboration is the concatenation of all 8 message fields in the output control block, producing content identical to the input data.
- 4 The outbound receives the input data and publishes the message to an external directory.

### 5.6.1. Create a project

The first step is to create and name a new project in eGate Enterprise Designer.

- 1 From the Enterprise Explorer pane of the Enterprise Designer, right-click the Repository and select **New Project**. A new project appears on the Project Explorer tree.
- 2 Rename the project (for this sample, **IMS\_MFS\_Sample**).

### 5.6.2 Create a Connectivity Map

- 1 In Enterprise Explorer, right-click the new project and select **New > Connectivity Map** from the shortcut menu.
- 2 The new Connectivity Map appears. From the Project Explorer, rename the new Connectivity Map **IMS\_MFS\_Sample\_CM**.

### Select the External Applications

For this sample, only the File External Application is required.

- 1 Click the **External Application** icon on the Connectivity Map toolbar.
- 2 Select the **File External Application** from the selection menu. The File External System is added to the Connectivity Map toolbar.


### Populate the Connectivity Map

Add the project components to the Connectivity Map by dragging and dropping the icons from the toolbar to the Connectivity Map canvas.

- 1 For this sample, add the following components to the Connectivity Map canvas as displayed in [Figure 31 on page 55](#):

- ◆ File External System (2)
- ◆ Service

**Figure 31** Connectivity Map with Components




- 2 Save your current changes to the Repository.

### 5.6.3. Create an OTD Using the IMS MFS Wizard

The IMS MFS Wizard creates a Object Type Definition from an MFS data file. A sample MFS file, **MFSSAMP.mfs** is provided on the Installation CD-ROM with the IMS eWay sample at ..\samples\ewims.. Copy this file to a temporary directory.


- 1 From the Project Explorer tree, right-click the **IMS\_MFS\_Sample** project and select **New > Object Type Definition** from the shortcut menu. The **Object Type Definition Wizard** appears.
- 2 From the Select Wizard Type box, select **IMS MFS Wizard** and click **Next**.
- 3 For step two of the wizard, Select Input Files, browse to the sample MFS file, **MFSSAMP.mfs**. Click **Select** to add the file to the Selected Files box (see Figure 32).

**Figure 32** IMS MFS Wizard - Select MSF file



- 4 Click Finish and save your changes to the Repository. The OTD Editor now displays the successfully created MFSSAMP OTD and the OTD is added to the Project Explorer tree (see Figure 33).

Figure 33 OTD Editor - MFSSAMP OTD



#### 5.6.4. Create the Collaboration Definitions

The next step in the sample is to create a Collaboration using the Collaboration Definition Wizard (Java), and Business Rules using the Collaboration Editor.

### The JavaCollaborationMFS Collaboration


The **JavaCollaborationMFS** Collaboration defines transactions from the inbound File application, converts the MFS data and sends the data to the outbound File application.

- 1 From the Project Explorer, right-click the current project and select **New > Collaboration Definition (Java)** from the shortcut menu. The **Collaboration Definition Wizard** appears.
- 2 Enter a Collaboration Definition name (for this sample **JavaCollaborationMFS**) and click **Next**.
- 3 For Step 2 of the wizard, **Select a Web Services Operation**, double-click **SeeBeyond > eWays > File > FileClient > receive**. The File Name field now displays **receive**. Click **Next**.



- 4 For Step 3 of the wizard, from the Select OTDs selection window, double-click **IMS\_MFS\_Sample > MFSSAMP**. The **MFSSAMP** OTD is added to the Selected OTDs field.
- 5 Click the **Up One Level** button to return to the Repository. From the Select OTDs selection window, double-click **SeeBeyond > eWays > File > FileClient**. The **FileClient** OTD is added to the Selected OTDs field (see Figure 34).

**Figure 34** Collaboration Definition Wizard (Java) - Select OTDs



- 6 Click **Finish**. The Collaboration Editor (Java) appears in the left pane of the Enterprise Designer and the **IMS\_MFS\_Collab** Collaboration (Java) is added to the Project Explorer tree.


### 5.6.5. The IMS\_MFS\_Collab Business Rules

The the **IMS\_MFS\_Sample** project uses one Collaboration created in the previous section, **IMS\_MFS\_Collab**.

#### IMS\_MFS\_Collab Business Rules

The **IMS\_MFS\_Collab** Collaboration contains the Business Rules displayed in [Figure 35 on page 58](#). These rules are created using the Collaboration Editor.

**Figure 35** IMS\_MFS\_Collab Collaboration Business Rules




- 7 For more information on how to create Business Rules using the Collaboration Editor see [Using the Collaboration Editor \(Java\)](#) on page 43 or see the *eGate Integrator User's Guide*.

### 5.6.6. Creating Collaboration Bindings

After the Collaboration has been written, the components are associated and Bindings are created in the Connectivity Map.

- 1 From the Project Explorer tree, double-click **IMS\_MFS\_Sample\_CM** to display the Connectivity Map.
- 2 Drag and drop the **IMS\_MFS\_Collab** Collaboration from the Project Explorer onto the Service (**Service1**).
- 3 Double-click **Service1** in the Connectivity Map. The **Service1** Binding dialog box appears.
- 4 From the **Service1** Binding dialog box, drag **FileClient input** (under Implemented Services) to the FileIn External Application.
- 5 From the **Service1** Binding dialog box, drag **FileClient\_1** (under Invoked Services) to the FileOut External Application (see [Figure 36 on page 59](#)).

**Figure 36** Connectivity Map - Connecting the Project's Components



- 6 Minimize the Service1 Binding dialog box and save your current changes to the Repository.

### 5.6.7. Configure the eWays

The IMS\_MFS\_Sample project uses two eWays, each represented in the Connectivity Map as a node between an External Application and the Collaboration.

- 1 Double-click the inbound **File eWay** located between the File1 External Application and the Collaboration in the Connectivity Map. Select **Inbound File eWay** in the Templates dialog box and click **OK**.
- 2 The Properties Sheet opens to the Inbound File eWay properties. Modify the properties for your system, include the settings for the **Inbound File eWay** in Table 9, and click **OK**.

**Table 9** Inbound File eWay Settings

Inbound eWay Connection Parameters	
Directory	C:/temp
Input file name	Input*.txt

- 3 Double-click the **Outbound File eWay** located between Service and the outbound File External Application, and select **Outbound File eWay**. Modify the File eWay properties for your system, including the settings in Table 10, and click **OK**.

**Table 10** Outbound File eWay Settings


Outbound eWay Connection Parameters	
Directory	C:/temp
Output file name	output%.dat

### 5.6.8. Creating an Environment

Environments include the external systems, Logical Hosts, integration servers and message servers used by a project and contain the configuration information for these components.

- 1 From the Enterprise Designer's Enterprise Explorer, click the **Environment Explorer** tab.
- 2 Right-click the Repository and select **New Environment**. A new Environment is added to the Environment Explorer tree.
- 3 Rename the new Environment to **IMS\_MFS\_Sample\_Env**.
- 4 Right-click **IMS\_MFS\_Sample\_Env** and select **New File External System**. Name the External System **FileExtSysIn** and select **Inbound File eWay** as the External System Type.
- 5 Right-click **IMS\_MFS\_Sample\_Env** and select **New File External System**. Name the External System **FileExtSysOut** and select **Outbound File eWay** as the External System Type.
- 6 Right-click **IMS\_MFS\_Sample\_Env** and select **New Logical Host**. The **LogicalHost1** box is added to the Environment and **LogicalHost1** is added to the Environment Editor tree.
- 7 Right-click **LogicalHost1** and select **New SeeBeyond Integration Server** from the shortcut menu. A new Integration Server (**IntegrationSvr1**) is added to the Environment Explorer tree under LogicalHost (see Figure 37).

Figure 37 Environment Editor




- 8 Save changes to the repository.

## 5.6.9 Creating and Activating the Deployment Profile

A Deployment Profile is used to assign services and message destinations to the integration server and message server.

- 1 From the Project Explorer tree, right-click the **IMS\_MFS\_Sample** project and select **New > Deployment Profile**.
- 2 Enter a name for the Deployment Profile (for this sample **IMS\_MFS\_Sample\_DP**). Make sure that the selected Environment is **IMS\_MFS\_Sample\_Env**. Click **OK**.
- 3 From the left pane of the Deployment Editor, drag the **FileIn -> Service1** to the **FileExtSysIn** box.
- 4 From the left pane of the Deployment Editor, drag the **Service1 -> FileOut** to the **FileExtSysOut** box.
- 5 Drag **Service1** to **IntegrationSvr1** in the **LogicalHost1** box (see Figure 38).

**Figure 38** Deployment Profile



- 6 Click **Activate**. When activation succeeds, save the changes to the Repository.

## 5.6.10. Running the Project

The following directions assume that the Enterprise Designer was downloaded to C:\ican50. If this is not the case, replace that location in the following directions with the appropriate location. A new LogicalHost must be downloaded for each project.

- 1 From the Enterprise Manager Downloads tab, double-click **Logical Host - for win32**.
- 2 Extract the file to the **C:\ican50\LogicalHost3** directory. You must specify the **LogicalHost3** directory for it to be created.
- 3 Navigate to the **C:\ican50\LogicalHost3\logicalhost\bootstrap\config** directory and open the **logical-host.properties** file using Notepad™.
- 4 Enter and save the following information in the appropriate fields:
  - ♦ Logical Host root directory: **C:\ican50\LogicalHost3**
  - ♦ Repository URL: **http://localhost:port number/repository name**

- ♦ Repository user name and password: *Your user name and password*
- ♦ Logical Host Environment name: **IMS\_MFS\_Sample\_Env**
- ♦ Logical Host name: **Localhost**

Save your changes to **logical-host.properties** and close the file.

- 5 Run the **bootstrap.bat** file located in the **C:\ican50\LogicalHost3\bootstrap\bin** directory.
- 6 Copy the sample input data file to the input directory.

---

## 5.7 The MFS\_IMS\_Sample Project

The MFS\_IMS\_Sample project uses the MFS OTD to compose IVTNO transaction messages.

- 1 An inbound File eWay supplies last names with which to create IVTNO "DISPLAY" transactions.
- 2 The MFS OTD is used to compose a transaction message for each supplied name, populating the OTD with the data and the transaction command "DISPLAY"
- 3 The OTD formats the message, which is passed thru the IMS eWay to the IMS application.
- 4 The response is sent back to the MFS OTD, allowing field-by-field access to its content.
- 5 An outbound File eWay spools select portions of each transaction response to a flat file.

### IMS Application Response Error Messages

The Java Collaboration in the MFS\_IMS\_Sample project includes a rule that causes each IMS application response to be logged as an error message in the Integration Server's log. This it is not an actual error, but is logged as such to display the response content as part of the demonstration without the need for the user to enable debug logging and contend with more extraneous messages.

### 5.7.1. Importing the MFS\_IMS\_Sample Project

To import the MFS\_IMS\_Sample project follow the directions from [Importing a Sample Project](#) on page 39, using the MFS\_IMS\_Sample.zip file.

### 5.7.2. Creating the Environment


Environments include the external systems, Logical Hosts, integration servers and message servers used by a project, and contain the configuration information for these components.

- 1 From the Enterprise Designer's Enterprise Explorer, click the **Environment Explorer** tab.
- 2 Right-click the Repository and select **New Environment**. A new Environment is added to the Environment Explorer tree.
- 3 Rename the new Environment to **MFS\_IMS\_Sample\_Env**.
- 4 Right-click **MFS\_IMS\_Sample\_Env** and select **New IMS External System**. Name the External System **IMSExtSys**. **IMSExtSys** is added to the Environment Editor.
- 5 Right-click **MFS\_IMS\_Sample\_Env** and select **New File External System**. Name the External System **FileExtSysIn** and select **Inbound File eWay** as the External System Type.

- 6 Right-click **MFS\_IMS\_Sample\_Env** and select **New File External System**. Name the External System **FileExtSysOut** and select **Outbound File eWay** as the External System Type.
- 7 Right-click **MFS\_IMS\_Sample\_Env** and select **New Logical Host**. The **LogicalHost1** box is added to the Environment and **LogicalHost1** is added to the Environment Editor tree.
- 8 Right-click **LogicalHost1** and select **New SeeBeyond Integration Server** from the shortcut menu. A new Integration Server (**IntegrationSvr1**) is added to the Environment Explorer tree under LogicalHost.

### 5.7.3. Configure the eWays

The MFS\_IMS\_Sample project uses three eWays, each represented in the Connectivity Map as a node between an External Application and the Collaboration (see Figure 39). eWays facilitate communication and movement of data between the External Applications and the eGate system.



### Configuring the File eWays

- 1 Double-click the **inbound File eWay** (see Figure 39). The Templates dialog box appears. Select **Inbound File eWay** in the Templates dialog box and click **OK**.
- 2 The Properties Sheet opens to the inbound File eWay properties. Modify the properties for your system, including the settings in Table 11, and click **OK**. The properties settings are saved for the eWay.

**Table 11** Inbound File eWay Settings

Inbound eWay Configuration Parameters	
Directory	C:/temp
Multiple records per file	True

- 3 Double-click the **outbound File eWay** located between **Service1** and the outbound **File2** External Application, and select **Outbound File eWay**. Modify the outbound File eWay configuration for your system, including the settings in Table 12, and click **OK**.



**Table 12** Outbound File eWay Settings

Outbound eWay Configuration Parameters	
Directory	C:/temp
Multiple records per file	True
Output file name	output%.dat

## Configuring the IMS eWay

The IMS eWay properties must be set in both the Project Explorer and Environment Explorer. For more information on the IMS eWay configuration properties and the Properties Sheet, see [Creating and Configuring the IMS eWay](#) on page 12, or see the *eGate Integrator User's Guide*.

### Modifying the IMS eWay Environment Explorer Properties

- 1 From the **Environment Explorer** tree, right-click the IMS External System (**IMSExtSys** in this sample), and select **Properties**. The Properties Sheet opens to the IMS eWay environment-configuration properties.
- 2 Modify the IMS eWay environment-configuration for your system, including the settings in Table 13, and click **OK**.

**Table 13** IMS eWay Environment Explorer Configuration Settings

IMS eWay (Environment Explorer) Configuration Parameters	
<b>TCPIP Configuration</b> Set as directed, otherwise use the default settings	
Port	Server port number
Server	Server name
<b>IRM Header Settings</b> Set as directed, otherwise use the default settings.	
IRM_TRNCOD	IVTNO
IRM_TRNCOD_SRC	MESSAGE

## 5.7.4 Creating and Activating the Deployment Profile

Deployment Profiles are specific instances of a project in a particular Environment. A Deployment Profile is created using the Enterprise Designer's Deployment Editor.

To create the **MFS\_IMS\_Sample\_DP** Deployment Profile do the following:

- 1 From the Enterprise Explorer's Project Explorer, right-click the project (**MSFS\_IMS\_Sample**) and select **New > Deployment Profile**.
- 2 From the **Create Deployment Profile for MFS\_IMS\_Sample** dialog box, enter a name for the Deployment Profile (for this sample **MFS\_IMS\_Sample\_DP**), and select **MFS\_IMS\_Sample\_Env** as the Environment. Click **OK**.

- 3 From the left pane of the Deployment Editor, drag **Service1** -> **IMS1** to the **IMSExtSys** window.
- 4 From the left pane of the Deployment Editor, drag **File1** -> **Service1** to the **FileExtSysIn** window.
- 5 From the left pane of the Deployment Editor, drag **Service1** -> **File2** to the **FileExtSysOut** window.
- 6 Drag **Service1** to **IntegrationSvr1** in the **LogicalHost1** window.
- 7 Click **Activate**. When activation succeeds, save the changes to the Repository.

### 5.7.5. Running the Project

The following directions assume that the Enterprise Designer was downloaded to C:\ican50. If this is not the case, replace that location in the following directions with the appropriate location. A new LogicalHost must be downloaded for each project.

- 1 From the Enterprise Manager Downloads tab, double-click **Logical Host - for win32**.
- 2 Extract the file to the C:\ican50\LogicalHost4 directory. You must specify the **LogicalHost4** directory for it to be created.
- 3 Navigate to the C:\ican50\LogicalHost4\logicalhost\bootstrap\config directory and open the logical-host.properties file using Notepad™.
- 4 Enter and save the following information in the appropriate fields:
  - ♦ Logical Host root directory: **C:\ican50\LogicalHost4**
  - ♦ Repository URL: **http://localhost:port number/repository name**
  - ♦ Repository user name and password: *Your user name and password*
  - ♦ Logical Host Environment name: **MFS\_IMS\_Sample\_Env**
  - ♦ Logical Host name: **Localhost**

Save your changes to **logical-host.properties** and close the file.

- 5 Run the **bootstrap.bat** file located in the C:\ican50\LogicalHost4\bootstrap\bin directory.
- 6 Copy the sample input data file to the input directory.

# Java Methods and Classes for the IMS eWay

The IMS eWay contains Java methods that are used to extend the functionality of the eWay. These methods are contained in the following class

---

## 6.1 The IMSClientETD Class

```

java.lang.Object
|
+ -- com.stc.eways.ims.EwayConnectionETDImpl
|
+ -- com.stc.eways.ims.IMSClientETD.

```

public class **IMSClientETD**

Extends com.stc.eway.ims.EwayConnectionETDImpl.

Implements com.stc.jcsre.ETDExt.

All implemented interfaces: com.stc.jcsre.ETD, com.stc.jcsre.ETDConstants, com.stc.jcsre.ETDExt.

### IMS Javadoc

The Javadoc is uploaded with the eWay's documentation file (**IMSeWayDocs.sar**) and downloaded from the Documentation tab of the Enterprise Manager. To access the full Javadoc, extract the Javadoc to an easily accessible folder, and double click the **index.html** file.

# Index

## A

alerting and logging  
alerts/status notifications 37

## B

binding  
  dialog box 32  
  the eWay components 31  
bindings 47  
bootstrap 36  
Business Process  
  creating 26  
Business Rule 43  
Business Rules Designer 44

## C

Collaboration  
  Editor  
    Java 42  
Collaboration Editor  
  Business Rules Designer 44  
  creating Business Rules 43  
Connectivity Map 41  
  creating 29  
  External Applications  
    creating 29  
    populating 30, 41

## D

Deployment Profile 35, 61

## E

eInsight 23  
  Business Process  
    creating 26  
  Business Process Designer 28  
    Business Rules Designer 28  
  Business Process Manager 23  
  IMSRequest 24  
  overview 23

  sample IMS Project  
    importing 25  
  sample IMS project 24  
Environment 49, 60  
  creating 32  
Environment Editor 33  
eWay  
  creating 13  
External Applications 41

## H

HWSP1435E Socket closed  
  error message 24, 39

## I

implementation 38  
IMS  
  Javadoc 67  
  overview 7  
IMS Connect 7, 8  
  software requirements 9  
IMS eWay  
  overview 7  
IMS External Application  
  creating 12  
IMSClientETD 38, 67  
installing  
  IMS eWay 10  
  sar files 11

## J

Java  
  Collaboration  
    using the editor 42  
  Collaboration Definitions 42  
  Collaboration Editor 43  
Javadoc 67  
  accessing 67  
  downloading 67  
  uploading 67

## L

logging 37  
Logical Host  
  Environment 32

## M

methods 67

## Index

- IMSCientETD Class 67
- MFS
  - sample project 54
  - wizard 55
    - overview 38
- Microsoft Internet Explorer 9

## O

- operating systems
  - supported 8

## P

- parameters
  - Class 15
  - Connector 15
  - IRM\_CLIENTID 17
  - IRM\_DESTID 17
  - IRM\_F1 18
  - IRM\_F2 18
  - IRM\_F3 18
  - IRM\_F4 19
  - IRM\_F5 19
  - IRM\_ID 20
  - IRM\_LEN 20
  - IRM\_LTERM 20
  - IRM\_RACF\_GRNAME 20
  - IRM\_RACF\_PW 21
  - IRM\_RACF\_USERID 21
  - IRM\_SOCT 21
  - IRM\_TIMER 21
  - IRM\_TRNCOD 22
  - IRM\_TRNCOD\_SRC 22
  - Port 16
  - Property Tag 15
  - Server 16
  - Type 16
- project
  - creating 25, 40
- properties 50, 64
  - Class 15
  - comments in Properties Sheet 15
  - configuring 33
  - configuring the IMS eWay 12
  - Connectivity Map 12, 15
  - Connector 15
  - descriptions in Properties Sheet 15
  - Environment Explorer 12
  - IRM Header 17
  - IRM\_CLIENTID 17
  - IRM\_DESTID 17
  - IRM\_F1 18
  - IRM\_F2 18

- IRM\_F3 18
- IRM\_F4 19
- IRM\_F5 19
- IRM\_ID 20
- IRM\_LEN 20
- IRM\_LTERM 20
- IRM\_RACF\_GRNAME 20
- IRM\_RACF\_PW 21
- IRM\_RACF\_USERID 21
- IRM\_SOCT 21
- IRM\_TIMER 21
- IRM\_TRNCOD 22
- IRM\_TRNCOD\_SRC 22
  - modifying existing 13
- overview 12
- Port 16
- Properties Sheet 13
- Property Tag 15
- Server 16
- TCPIP Configuration 16
- Type 16
- Properties Sheet 13
  - comments pane 15
  - description pane 15
  - overview 13

## R

- RACF 9
- running the project 36, 53

## S

- samples
  - importing 38
  - Java Collaboration samples 38
- SeeBeyond Integration Server Environment 32
- system requirements 9
  - external 9

## U

- user interface requirements 9

## W

- Windows 9