



OpenMP API User's Guide

Sun™ Studio 11

Sun Microsystems, Inc.
www.sun.com

Part No.819-3694-10
November 2005, Revision A

Submit comments about this document at: <http://www.sun.com/hwdocs/feedback>

Copyright © 2005 Sun Microsystems, Inc., 4150 Network Circle, Santa Clara, California 95054, U.S.A. All rights reserved.

U.S. Government Rights - Commercial software. Government users are subject to the Sun Microsystems, Inc. standard license agreement and applicable provisions of the FAR and its supplements. Use is subject to license terms.

This distribution may include materials developed by third parties.

Parts of the product may be derived from Berkeley BSD systems, licensed from the University of California. UNIX is a registered trademark in the U.S. and in other countries, exclusively licensed through X/Open Company, Ltd.

Sun, Sun Microsystems, the Sun logo, Java, and JavaHelp are trademarks or registered trademarks of Sun Microsystems, Inc. in the U.S. and other countries. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. in the U.S. and other countries. Products bearing SPARC trademarks are based upon architecture developed by Sun Microsystems, Inc.

This product is covered and controlled by U.S. Export Control laws and may be subject to the export or import laws in other countries. Nuclear, missile, chemical biological weapons or nuclear maritime end uses or end users, whether direct or indirect, are strictly prohibited. Export or reexport to countries subject to U.S. embargo or to entities identified on U.S. export exclusion lists, including, but not limited to, the denied persons and specially designated nationals lists is strictly prohibited.

DOCUMENTATION IS PROVIDED "AS IS" AND ALL EXPRESS OR IMPLIED CONDITIONS, REPRESENTATIONS AND WARRANTIES, INCLUDING ANY IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE OR NON-INFRINGEMENT, ARE DISCLAIMED, EXCEPT TO THE EXTENT THAT SUCH DISCLAIMERS ARE HELD TO BE LEGALLY INVALID.

Copyright © 2005 Sun Microsystems, Inc., 4150 Network Circle, Santa Clara, California 95054, Etats-Unis. Tous droits réservés.

L'utilisation est soumise aux termes de la Licence.

Cette distribution peut comprendre des composants développés par des tierces parties.

Des parties de ce produit pourront être dérivées des systèmes Berkeley BSD licenciés par l'Université de Californie. UNIX est une marque déposée aux Etats-Unis et dans d'autres pays et licenciée exclusivement par X/Open Company, Ltd.

Sun, Sun Microsystems, le logo Sun, Java, et JavaHelp sont des marques de fabrique ou des marques déposées de Sun Microsystems, Inc. aux Etats-Unis et dans d'autres pays. Toutes les marques SPARC sont utilisées sous licence et sont des marques de fabrique ou des marques déposées de SPARC International, Inc. aux Etats-Unis et dans d'autres pays. Les produits portant les marques SPARC sont basés sur une architecture développée par Sun Microsystems, Inc.

Ce produit est soumis à la législation américaine en matière de contrôle des exportations et peut être soumis à la réglementation en vigueur dans d'autres pays dans le domaine des exportations et importations. Les utilisations, ou utilisateurs finaux, pour des armes nucléaires, des missiles, des armes biologiques et chimiques ou du nucléaire maritime, directement ou indirectement, sont strictement interdites. Les exportations ou réexportations vers les pays sous embargo américain, ou vers des entités figurant sur les listes d'exclusion d'exportation américaines, y compris, mais de manière non exhaustive, la liste de personnes qui font objet d'un ordre de ne pas participer, d'une façon directe ou indirecte, aux exportations des produits ou des services qui sont régis par la législation américaine en matière de contrôle des exportations et la liste de ressortissants spécifiquement désignés, sont rigoureusement interdites.

LA DOCUMENTATION EST FOURNIE "EN L'ÉTAT" ET TOUTES AUTRES CONDITIONS, DECLARATIONS ET GARANTIES EXPRESSES OU TACITES SONT FORMELLEMENT EXCLUES, DANS LA MESURE AUTORISEE PAR LA LOI APPLICABLE, Y COMPRIS NOTAMMENT TOUTE GARANTIE IMPLICITE RELATIVE A LA QUALITE MARCHANDE, A L'APTITUDE A UNE UTILISATION PARTICULIERE OU A L'ABSENCE DE CONTREFAÇON.



Adobe PostScript

Contents

- Before You Begin ix**
 - Typographic Conventions ix
 - Shell Prompts x
 - Supported Platforms x
 - Accessing Sun Studio Software and Man Pages xi
 - Accessing Compilers and Tools Documentation xv
 - Accessing Related Solaris Documentation xviii
 - Resources for Developers xviii
 - Contacting Sun Technical Support xix
 - Sending Your Comments xix
- 1. Introducing the OpenMP API 1-1**
 - 1.1 Where to Find the OpenMP Specifications 1-1
 - 1.2 Special Conventions Used Here 1-2
- 2. Nested Parallelism 2-1**
 - 2.1 The Execution Model 2-1
 - 2.2 Control of Nested Parallelism 2-2
 - 2.2.1 **OMP_NESTED** 2-2
 - 2.2.2 **SUNW_MP_MAX_POOL_THREADS** 2-3

- 2.2.3 **SUNW_MP_MAX_NESTED_LEVELS** 2-4
- 2.3 Using OpenMP Library Routines Within Nested Parallel Regions 2-7
- 2.4 Some Tips on Using Nested Parallelism 2-10
- 3. Automatic Scoping of Variables 3-1**
 - 3.1 The Autoscopying Data Scope Clause 3-1
 - 3.1.1 **__AUTO** Clause 3-1
 - 3.1.2 **DEFAULT(__AUTO)** Clause 3-2
 - 3.2 Scoping Rules 3-2
 - 3.2.1 Scoping Rules For Scalar Variables 3-2
 - 3.2.2 Scoping Rules for Arrays 3-3
 - 3.3 General Comments About Autoscopying 3-3
 - 3.3.1 Autoscopying Rules for Fortran 95: 3-3
 - 3.3.2 Autoscopying Rules for C/C++: 3-4
 - 3.4 Checking the Results of Autoscopying 3-5
 - 3.5 Known Limitations of the Current Implementation 3-9
- 4. Implementation-Defined Behaviors 4-1**
- 5. Compiling for OpenMP 5-1**
 - 5.1 Compiler Options To Use 5-1
 - 5.2 Fortran 95 OpenMP Validation 5-3
 - 5.3 OpenMP Environment Variables 5-5
 - 5.4 Processor Binding 5-8
 - 5.5 Stacks and Stack Sizes 5-11
- 6. Converting to OpenMP 6-1**
 - 6.1 Converting Legacy Fortran Directives 6-1
 - 6.1.1 Converting Sun-Style Fortran Directives 6-2
 - 6.1.2 Converting Cray-Style Fortran Directives 6-4

6.2	Converting Legacy C Pragmas	6-4
6.2.1	Issues Between Legacy C Pragmas and OpenMP	6-6
7.	Performance Considerations	7-1
7.1	Some General Recommendations	7-1
7.2	False Sharing And How To Avoid It	7-5
7.2.1	What Is <i>False Sharing</i> ?	7-5
7.2.2	Reducing False Sharing	7-6
7.3	Operating System Tuning Features	7-6
A.	Placement of Clauses on Directives	A-1
	Index	Index-1

Tables

TABLE 5-1	OpenMP Environment Variables	5–5
TABLE 5-2	Multiprocessing Environment Variables	5–6
TABLE 6-1	Converting Sun Parallelization Directives to OpenMP	6–2
TABLE 6-2	DOALL Qualifier Clauses and OpenMP Equivalent Clauses	6–2
TABLE 6-3	SCHEDTYPE Scheduling and OpenMP <code>schedule</code> Equivalents	6–3
TABLE 6-4	OpenMP Equivalents for Cray-Style DOALL Qualifier Clauses	6–4
TABLE 6-5	Converting Legacy C Parallelization Pragmas to OpenMP	6–5
TABLE 6-6	<code>taskloop</code> Optional Clauses and OpenMP Equivalents	6–5
TABLE 6-7	SCHEDTYPE Scheduling and OpenMP <code>schedule</code> Equivalents	6–6
TABLE A-1	Pragmas Where Clauses Can Appear	A–1

Before You Begin

The *OpenMP API User's Guide* summarizes the OpenMP Fortran 95, C, and C++ application program interface (API) for building multiprocessing applications. Sun™ Studio compilers support the OpenMP API.

This guide is intended for scientists, engineers, and programmers who have a working knowledge of the Fortran, C, or C++ languages, and the OpenMP parallel programming model. Familiarity with the Solaris™ operating environment or UNIX® in general is also assumed.

Typographic Conventions

TABLE P-1 Typeface Conventions

Typeface	Meaning	Examples
AaBbCc123	The names of commands, files, and directories; on-screen computer output	Edit your <code>.login</code> file. Use <code>ls -a</code> to list all files. % You have mail.
AaBbCc123	What you type, when contrasted with on-screen computer output	% su Password:
<i>AaBbCc123</i>	Book titles, new words or terms, words to be emphasized	Read Chapter 6 in the <i>User's Guide</i> . These are called <i>class</i> options. You <i>must</i> be superuser to do this.
<code>AaBbCc123</code>	Command-line placeholder text; replace with a real name or value	To delete a file, type <code>rm filename</code> .

TABLE P-2 Code Conventions

Code Symbol	Meaning	Notation	Code Example
[]	Brackets contain arguments that are optional.	<code>O[n]</code>	<code>O4, O</code>
{ }	Braces contain a set of choices for a required option.	<code>d{y n}</code>	<code>dy</code>
	The “pipe” or “bar” symbol separates arguments, only one of which may be chosen.	<code>B{dynamic static}</code>	<code>Bstatic</code>
:	The colon, like the comma, is sometimes used to separate arguments.	<code>Rdir[:dir]</code>	<code>R/local/libs:/U/a</code>
...	The ellipsis indicates omission in a series.	<code>xinline=<i>fl</i>[,...<i>fn</i>]</code>	<code>xinline=alpha,dos</code>

Shell Prompts

Shell	Prompt
C shell	<i>machine-name%</i>
C shell superuser	<i>machine-name#</i>
Bourne shell and Korn shell	\$
Superuser for Bourne shell and Korn shell	#

Supported Platforms

This Sun Studio release supports systems that use the SPARC® and x86 families of processor architectures: UltraSPARC®, SPARC64, AMD64, Pentium, and Xeon EM64T. The supported systems for the version of the Solaris Operating System you are running are available in the hardware compatibility lists at <http://www.sun.com/bigadmin/hcl>. These documents cite any implementation differences between the platform types.

In this document, these x86 related terms mean the following:

- “x86” refers to the larger family of 64-bit and 32-bit x86 compatible products.
- “x64” points out specific 64-bit information about AMD64 or EM64T systems.
- “32-bit x86” points out specific 32-bit information about x86 based systems.

For supported systems, see the hardware compatibility lists.

Accessing Sun Studio Software and Man Pages

The Sun Studio software and its man pages are not installed into the standard `/usr/bin/` and `/usr/share/man` directories. To access the software, you must have your `PATH` environment variable set correctly (see [“Accessing the Software” on page xi](#)). To access the man pages, you must have your `MANPATH` environment variable set correctly (see [“Accessing the Man Pages” on page xii](#)).

For more information about the `PATH` variable, see the `csh(1)`, `sh(1)`, `ksh(1)`, and `bash(1)` man pages. For more information about the `MANPATH` variable, see the `man(1)` man page. For more information about setting your `PATH` variable and `MANPATH` variable to access this release, see the installation guide or your system administrator.

Note – The information in this section assumes that your Sun Studio software is installed in the `/opt` directory on Solaris platforms and in the `/opt/sun` directory on Linux platforms. If your software is not installed in the default directory, ask your system administrator for the equivalent path on your system.

Accessing the Software

Use the steps below to determine whether you need to change your `PATH` variable to access the software.

To Determine Whether You Need to Set Your PATH Environment Variable

1. Display the current value of the PATH variable by typing the following at a command prompt.

```
% echo $PATH
```

2. On Solaris platforms, review the output to find a string of paths that contain /opt/SUNWspro/bin. On Linux platforms, review the output to find a string of paths that contain /opt/sun/sunstudio11/bin.

If you find the path, your PATH variable is already set to access the software. If you do not find the path, set your PATH environment variable by following the instructions in the next procedure.

To Set Your PATH Environment Variable to Enable Access to the Software

- On Solaris platforms, add the following path to your PATH environment variable. If you have previously installed Forte Developer software, Sun ONE Studio software, or another release of Sun Studio software, add the following path before the paths to those installations.

```
/opt/SUNWspro/bin
```

- On Linux platforms, add the following path to your PATH environment variable.

```
/opt/sun/sunstudio10u1/bin
```

Accessing the Man Pages

Use the following steps to determine whether you need to change your MANPATH variable to access the man pages.

To Determine Whether You Need to Set Your MANPATH Environment Variable

1. Request the dbx man page by typing the following at a command prompt.

```
% man dbx
```

2. Review the output, if any.

If the `dbx(1)` man page cannot be found or if the man page displayed is not for the current version of the software, follow the instructions in the next procedure to set your `MANPATH` environment variable.

To Set Your `MANPATH` Environment Variable to Enable Access to the Man Pages

- **On Solaris platforms, add the following path to your `MANPATH` environment variable.**

```
/opt/SUNWspro/man
```

- **On Linux platforms, add the following path to your `MANPATH` environment variable.**

```
/opt/sun/sunstudio11/man
```

Accessing the Integrated Development Environment

The Sun Studio integrated development environment (IDE) provides modules for creating, editing, building, debugging, and analyzing the performance of a C, C++, or Fortran application.

The command to start the IDE is `sunstudio`. For details on this command, see the `sunstudio(1)` man page.

The correct operation of the IDE depends on the IDE being able to find the core platform. The `sunstudio` command looks for the core platform in two locations:

- The command looks first in the default installation directory,
`/opt/netbeans/3.5V11` on Solaris platforms and
`/opt/sun/netbeans/3.5V11` on Linux platforms.
- If the command does not find the core platform in the default directory, it assumes that the directory that contains the IDE and the directory that contains the core platform are both installed in or mounted to the same location. For example, on Solaris platforms, if the path to the directory that contains the IDE is `/foo/SUNWspro`, the command looks for the core platform in `/foo/netbeans/3.5V11`. On Linux platforms, if the path to the directory that contains the IDE is `/foo/sunstudio11`, the command looks for the core platform in `/foo/netbeans/3.5V11`.

If the core platform is not installed or mounted to either of the locations where the `sunstudio` command looks for it, then each user on a client system must set the environment variable `SPRO_NETBEANS_HOME` to the location where the core platform is installed or mounted (*/installation_directory/netbeans/3.5V11*).

On Solaris platforms, each user of the IDE also must add */installation_directory/SUNWspro/bin* to their `$PATH` in front of the path to any other release of Forte Developer software, Sun ONE Studio software, or Sun Studio software. On Linux platforms, each user of the IDE also must add */installation_directory/sunstudio11/bin* to their `$PATH` in front of the path to any other release of Sun Studio software.

The path */installation_directory/netbeans/3.5V11/bin* should not be added to the user's `$PATH`.

Accessing Compilers and Tools Documentation

You can access the documentation at the following locations:

- The documentation is available from the documentation index that is installed with the software on your local system or network at
file:/opt/SUNWspro/docs/index.html on Solaris platforms and at
file:/opt/sun/sunstudio11/docs/index.html on Linux platforms.

If your software is not installed in the /opt directory on a Solaris platform or the /opt/sun directory on a Linux platform, ask your system administrator for the equivalent path on your system.

- Most manuals are available from the docs.sun.comsm web site. The following titles are available through your installed software on Solaris platforms only:
 - *Standard C++ Library Class Reference*
 - *Standard C++ Library User's Guide*
 - *Tools.h++ Class Library Reference*
 - *Tools.h++ User's Guide*
- The release notes for both Solaris platforms and Linux platforms are available from the docs.sun.com web site.
- Online help for all components of the IDE is available through the Help menu, as well as through Help buttons on many windows and dialog boxes, in the IDE.

The docs.sun.com web site (<http://docs.sun.com>) enables you to read, print, and buy Sun Microsystems manuals through the Internet. If you cannot find a manual, see the documentation index that is installed with the software on your local system or network.

Note – Sun is not responsible for the availability of third-party Web sites mentioned in this document. Sun does not endorse and is not responsible or liable for any content, advertising, products, or other materials that are available on or through such sites or resources. Sun will not be responsible or liable for any actual or alleged damage or loss caused by or in connection with the use of or reliance on any such content, goods, or services that are available on or through such sites or resources.

Documentation in Accessible Formats

The documentation is provided in accessible formats that are readable by assistive technologies for users with disabilities. You can find accessible versions of documentation as described in the following table. If your software is not installed in the `/opt` directory, ask your system administrator for the equivalent path on your system.

Type of Documentation	Format and Location of Accessible Version
Manuals (except third-party manuals)	HTML at http://docs.sun.com
Third-party manuals: <ul style="list-style-type: none">• <i>Standard C++ Library Class Reference</i>• <i>Standard C++ Library User's Guide</i>• <i>Tools.h++ Class Library Reference</i>• <i>Tools.h++ User's Guide</i>	HTML in the installed software on Solaris platforms through the documentation index at <code>file:/opt/SUNWspr0/docs/index.html</code>
Readmes	HTML on the developer portal at http://developers.sun.com/prodtech/cc/documentation/ss11/mr/READMEs
Man pages	HTML in the installed software through the documentation index at <code>file:/opt/SUNWspr0/docs/index.html</code> on Solaris platforms, and at <code>file:/opt/sun/sunstudio11/docs/index.html</code> on Linux platforms,
Online help	HTML available through the Help menu and Help buttons in the IDE
Release notes	HTML at http://docs.sun.com

Related Compilers and Tools Documentation

The following table describes related documentation that is available at `file:/opt/SUNWspro/docs/index.html` and <http://docs.sun.com>. If your software is not installed in the `/opt` directory, ask your system administrator for the equivalent path on your system

Document Title	Description
<i>Fortran Programming Guide</i>	Describes how to write effective Fortran code on Solaris environments; input/output, libraries, performance, debugging, and parallel processing.
<i>Fortran Library Reference</i>	Details the Fortran library and intrinsic routines
<i>Fortran User's Guide</i>	Describes the compile-time environment and command-line options for the f95 compiler. Also includes guidelines for migrating legacy f77 programs to f95.
<i>C User's Guide</i>	Describes the compile-time environment and command-line options for the cc compiler.
<i>C++ User's Guide</i>	Describes the compile-time environment and command-line options for the CC compiler.
<i>Numerical Computation Guide</i>	Describes issues regarding the numerical accuracy of floating-point computations.

Accessing Related Solaris Documentation

The following table describes related documentation that is available through the `docs.sun.com` web site.

Document Collection	Document Title	Description
Solaris Reference Manual Collection	See the titles of man page sections.	Provides information about the Solaris OS.
Solaris Software Developer Collection	<i>Linker and Libraries Guide</i>	Describes the operations of the Solaris link-editor and runtime linker.
Solaris Software Developer Collection	<i>Multithreaded Programming Guide</i>	Covers the POSIX and Solaris threads APIs, programming with synchronization objects, compiling multithreaded programs, and finding tools for multithreaded programs.

Resources for Developers

Visit <http://developers.sun.com/prodtech/cc> to find these frequently updated resources:

- Articles on programming techniques and best practices
- A knowledge base of short programming tips
- Documentation of compilers and tools components, as well as corrections to the documentation that is installed with your software
- Information on support levels
- User forums
- Downloadable code samples
- New technology previews

You can find additional resources for developers at <http://developers.sun.com>.

Contacting Sun Technical Support

If you have technical questions about this product that are not answered in this document, go to:

<http://www.sun.com/service/contacting>

Sending Your Comments

Sun is interested in improving its documentation and welcomes your comments and suggestions. Submit your comments to Sun at this URL:

<http://www.sun.com/hwdocs/feedback>

Please include the part number (819-3694-10) of your document in the subject line of your email.

Introducing the OpenMP API

The OpenMP™ Application Program Interface is a portable, parallel programming model for shared memory multiprocessor architectures, developed in collaboration with a number of computer vendors. The specifications were created and are published by the OpenMP Architecture Review Board.

The OpenMP API is the recommended parallel programming model for all Sun Studio compilers on Solaris™ OS platforms. See [Chapter 6](#) for guidelines on converting legacy Fortran and C parallelization directives to OpenMP.

1.1 Where to Find the OpenMP Specifications

The material presented in this manual describes issues specific to the Sun Studio implementation of the OpenMP API. For complete details you must refer to the OpenMP specification documents. This manual makes direct references to sections in the OpenMP 2.5 API specification.

The OpenMP 2.5 specification for C, C++, and Fortran 95 can be found on the official OpenMP website, <http://www.openmp.org/>.

Additional information about OpenMP including tutorials and other resources for developers can be found on the cOMPunity website, <http://www.compunity.org/>

Latest information about the Sun Studio compiler releases and their implementation of the OpenMP API can be found on the Sun Developer Network portal, <http://developers.sun.com/sunstudio>

1.2 Special Conventions Used Here

In the tables and examples that follow, Fortran directives and source code are shown in upper case, but are case-insensitive.

The term *structured-block* refers to a block of Fortran or C/C++ statements having no transfers into or out of the block.

Constructs within square brackets, [...], are optional.

Throughout this manual, “Fortran” refers to the Fortran 95 language and compiler, **f95**.

The terms “directive” and “pragma” are used interchangeably in this manual.

Nested Parallelism

This chapter discusses the features of OpenMP nested parallelism.

2.1 The Execution Model

OpenMP uses a fork-join model of parallel execution. When a thread encounters a parallel construct, the thread creates a team composed of itself and some additional (possibly zero) number of threads. The encountering thread becomes the master of the new team. The other threads of the team are called slave threads of the team. All team members execute the code inside the parallel construct. When a thread finishes its work within the parallel construct, it waits at the implicit barrier at the end of the parallel construct. When all team members have arrived at the barrier, the threads can leave the barrier. The master thread continues execution of user code beyond the end of the parallel construct, while the slave threads wait to be summoned to join other teams.

OpenMP parallel regions can be nested inside each other. If nested parallelism is disabled, then the new team created by a thread encountering a parallel construct inside a parallel region consists only of the encountering thread. If nested parallelism is enabled, then the new team may consist of more than one thread.

The OpenMP runtime library maintains a pool of threads that can be used as slave threads in parallel regions. When a thread encounters a parallel construct and needs to create a team of more than one thread, the thread will check the pool and grab idle threads from the pool, making them slave threads of the team. The master thread might get fewer slave threads than it needs if there is not a sufficient number of idle threads in the pool. When the team finishes executing the parallel region, the slave threads return to the pool.

2.2 Control of Nested Parallelism

Nested parallelism can be controlled at runtime by setting various environment variables prior to execution of the program.

2.2.1 **OMP_NESTED**

Nested parallelism can be enabled or disabled by setting the **OMP_NESTED** environment variable or calling `omp_set_nested()`.

The following example shows a team of more than one thread executing a nested parallel region when nested parallelism is enabled.

CODE EXAMPLE 2-1 Nested Parallelism Example

```
#include <omp.h>
#include <stdio.h>
void report_num_threads(int level)
{
    #pragma omp single
    {
        printf("Level %d: number of threads in the team - %d\n",
              level, omp_get_num_threads());
    }
}

int main()
{
    omp_set_dynamic(0);
    #pragma omp parallel num_threads(2)
    {
        report_num_threads(1);
        #pragma omp parallel num_threads(2)
        {
            report_num_threads(2);
            #pragma omp parallel num_threads(2)
            {
                report_num_threads(3);
            }
        }
    }
    return(0);
}
```


Compiling and running this program with nested parallelism enabled produces the following output:

```
% setenv OMP_NESTED TRUE
% a.out
Level 1: number of threads in the team - 2
Level 2: number of threads in the team - 2
Level 2: number of threads in the team - 2
Level 3: number of threads in the team - 2
Level 3: number of threads in the team - 2
Level 3: number of threads in the team - 2
Level 3: number of threads in the team - 2
```

Compare with running the same program but with nested parallelism disabled:

```
% setenv OMP_NESTED FALSE
% a.out
Level 1: number of threads in the team - 2
Level 2: number of threads in the team - 1
Level 3: number of threads in the team - 1
Level 2: number of threads in the team - 1
Level 3: number of threads in the team - 1
```

2.2.2 **SUNW_MP_MAX_POOL_THREADS**

The OpenMP runtime library maintains a pool of threads that can be used as slave threads in parallel regions. Setting the **SUNW_MP_MAX_POOL_THREADS** environment variable controls the number of threads in the pool. The default value is 1023.

The thread pool consists of only non-user threads that the runtime library creates. It does not include the initial thread or any thread created explicitly by the user's program. If this environment variable is set to zero, the thread pool will be empty and all parallel regions will be executed by one thread.

The following example shows that a parallel region can get fewer threads if there are not sufficient threads in the pool. The code is the same as above. The number of threads needed for all the parallel regions to be active at the same time is 8. The pool needs to contain at least 7 threads. If we set **SUNW_MP_MAX_POOL_THREADS** to 5,

two of the four inner-most parallel regions may not be able to get all the slave threads they ask for. One possible result is shown below.

```
% setenv OMP_NESTED TRUE
% setenv SUNW_MP_MAX_POOL_THREADS 5
% a.out
Level 1: number of threads in the team - 2
Level 2: number of threads in the team - 2
Level 2: number of threads in the team - 2
Level 3: number of threads in the team - 2
Level 3: number of threads in the team - 2
Level 3: number of threads in the team - 1
Level 3: number of threads in the team - 1
```

2.2.3 **SUNW_MP_MAX_NESTED_LEVELS**

The environment variable **SUNW_MP_MAX_NESTED_LEVELS** controls the maximum depth of nested active parallel regions that require more than one thread.

Any active parallel region that has an active nested depth greater than the value of this environment variable will be executed by only one thread. A parallel region is considered active if it is an OpenMP parallel region whose **IF** clause, if specified, evaluates to true. Only active parallel regions are counted. The default maximum number of active nesting levels is 4.

The following code will create 4 levels of nested parallel regions. If **SUNW_MP_MAX_NESTED_LEVELS** is set to 2, then nested parallel regions at nested depth of 3 and 4 are executed single-threaded.

```

#include <omp.h>
#include <stdio.h>
#define DEPTH 5
void report_num_threads(int level)
{
    #pragma omp single
    {
        printf("Level %d: number of threads in the team - %d\n",
            level, omp_get_num_threads());
    }
}
void nested(int depth)
{
    if (depth == DEPTH)
        return;

    #pragma omp parallel num_threads(2)
    {
        report_num_threads(depth);
        nested(depth+1);
    }
}
int main()
{
    omp_set_dynamic(0);
    omp_set_nested(1);
    nested(1);
    return(0);
}

```

Compiling and running this program with a maximum nesting level of 4 gives the following possible output. (Actual results will depend on how the OS schedules threads.)

```

% setenv SUNW_MP_MAX_NESTED_LEVELS 4
% a.out |sort +2n
Level 1: number of threads in the team - 2
Level 2: number of threads in the team - 2
Level 2: number of threads in the team - 2
Level 3: number of threads in the team - 2
Level 3: number of threads in the team - 2
Level 3: number of threads in the team - 2
Level 3: number of threads in the team - 2
Level 4: number of threads in the team - 2
Level 4: number of threads in the team - 2
Level 4: number of threads in the team - 2
Level 4: number of threads in the team - 2
Level 4: number of threads in the team - 2
Level 4: number of threads in the team - 2
Level 4: number of threads in the team - 2
Level 4: number of threads in the team - 2

```

Running with the nesting level set at 2 gives the following as a possible result:

```

% setenv SUNW_MP_MAX_NESTED_LEVELS 2
% a.out |sort +2n
Level 1: number of threads in the team - 2
Level 2: number of threads in the team - 2
Level 2: number of threads in the team - 2
Level 3: number of threads in the team - 1
Level 3: number of threads in the team - 1
Level 3: number of threads in the team - 1
Level 3: number of threads in the team - 1
Level 4: number of threads in the team - 1
Level 4: number of threads in the team - 1
Level 4: number of threads in the team - 1
Level 4: number of threads in the team - 1

```

Again, these examples only show some *possible* results. Actual results will depend on how the OS schedules threads.

2.3 Using OpenMP Library Routines Within Nested Parallel Regions

Calls to the following OpenMP routines within nested parallel regions deserve some discussion.

- `omp_set_num_threads()`
- `omp_get_max_threads()`
- `omp_set_dynamic()`
- `omp_get_dynamic()`
- `omp_set_nested()`
- `omp_get_nested()`

The 'set' calls affect only the parallel regions at the same or inner nesting levels encountered by the calling thread. They do not affect parallel regions encountered by other threads, and they do not affect parallel regions the calling thread will later encounter in any outer levels.

The 'get' calls will return the values set by the calling thread. When a team is created, the slave threads will inherit the values from the master thread.

CODE EXAMPLE 2-2 Calls to OpenMP Routines Within Parallel Regions

```
#include <stdio.h>
#include <omp.h>
int main()
{
    omp_set_nested(1);
    omp_set_dynamic(0);
    #pragma omp parallel num_threads(2)
    {
        if (omp_get_thread_num() == 0)
            omp_set_num_threads(4);          /* line A */
        else
            omp_set_num_threads(6);          /* line B */

        /* The following statement will print out
        *
        * 0: 2 4
        * 1: 2 6
        *
        * omp_get_num_threads() returns the number
        * of the threads in the team, so it is
        * the same for the two threads in the team.
        */
        printf("%d: %d %d\n", omp_get_thread_num(),
              omp_get_num_threads(),
              omp_get_max_threads());

        /* Two inner parallel regions will be created
        * one with a team of 4 threads, and the other
        * with a team of 6 threads.
        */
        #pragma omp parallel
        {
            #pragma omp master
            {
                /* The following statement will print out
                *
                * Inner: 4
                * Inner: 6
                */
                printf("Inner: %d\n", omp_get_num_threads());
            }
            omp_set_num_threads(7);          /* line C */
        }
    }
}
```

```

        /* Again two inner parallel regions will be created,
        * one with a team of 4 threads, and the other
        * with a team of 6 threads.
        *
        * The omp_set_num_threads(7) call at line C
        * has no effect here, since it affects only
        * parallel regions at the same or inner nesting
        * level as line C.
        */

        #pragma omp parallel
        {
            printf("count me.\n");
        }
    }
    return(0);
}

```

Compiling and running this program gives the following as one possible result:

```

% a.out
0: 2 4
Inner: 4
1: 2 6
Inner: 6
count me.
count me.
count me.
count me.
count me.
count me.
count me.
count me.
count me.
count me.
count me.

```

2.4 Some Tips on Using Nested Parallelism

- Nesting parallel regions provides an immediate way to allow more threads to participate in the computation.

For example, suppose you have a program that contains two levels of parallelism and the degree of parallelism at each level is 2. Also, suppose your system has four cpus and you want use all four CPUs to speed up the execution of this program. Just parallelizing any one level will use only two CPUs. You want to parallelize both levels.

- Nesting parallel regions can easily create too many threads and oversubscribe the system. Set **SUNW_MP_MAX_POOL_THREADS** and **SUNW_MP_MAX_NESTED_LEVELS** appropriately to limit the number of threads in use and prevent runaway oversubscription.
- Creating nested parallel regions adds overhead. If there is enough parallelism at the outer level and the load is balanced, generally it will be more efficient to use all the threads at the outer level of the computation than to create nested parallel regions at the inner levels.

For example, suppose you have a program that contains two levels of parallelism. The degree of parallelism at the outer level is 4 and the load is balanced. You have a system with four CPUs and want to use all four CPUs to speed up the execution of this program. Then, in general, using all 4 threads for the outer level could yield better performance than using 2 threads for the outer parallel region, and using the other 2 threads as slave threads for the inner parallel regions.

Automatic Scoping of Variables

Declaring the scope attributes of variables in an OpenMP parallel region is called *scoping*. In general, if a variable is scoped as **SHARED**, all threads share a single copy of the variable. If a variable is scoped as **PRIVATE**, each thread has its own copy of the variable. OpenMP has a rich data environment. In addition to **SHARED** and **PRIVATE**, the scope of a variable can also be declared **FIRSTPRIVATE**, **LASTPRIVATE**, **REDUCTION**, or **THREADPRIVATE**.

OpenMP requires the user to declare the scope of each variable used in a parallel region. This is a tedious and error-prone process and many find this to be the hardest part of using OpenMP to parallelize programs.

The Sun Studio C, C++, and Fortran 95 compilers provide an automatic scoping feature. The compilers analyze the execution and synchronization pattern of a parallel region and determine automatically what the scope of a variable should be, based on a set of scoping rules.

3.1 The Autoscopying Data Scope Clause

The autoscopying data scope clause is a Sun extension to the OpenMP specification. A user can specify a variable to be autoscoped by using one of the following two clauses.

3.1.1 **__AUTO** Clause

__AUTO (*list-of-variables*) on Fortran 95 directives
__auto (*list-of-variables*) on C and C++ pragmas

The compiler will determine the scope of the variables listed within a parallel region. (Note the *two* underscores before **AUTO** and **auto**).

The `__AUTO` or `__auto` clause can appear on a **PARALLEL**, **PARALLEL DO**, **PARALLEL SECTIONS**, or on a Fortran 95 **PARALLEL WORKSHARE** directive.

If a variable is listed in the clause, then it cannot be specified in any other data scope clause.

3.1.2 **DEFAULT (__AUTO)** Clause

DEFAULT (__AUTO) on Fortran 95 directives
default (__auto) on C and C++ pragmas

Set the default scoping in this parallel region to be `__AUTO`.

The **DEFAULT (__AUTO)** clause can appear on a **PARALLEL**, **PARALLEL DO**, **PARALLEL SECTIONS**, or on a Fortran 95 **PARALLEL WORKSHARE** directive.

3.2 Scoping Rules

Under automatic scoping, the compiler applies the following rules to determine the scope of a variable in a parallel region.

These rules do not apply to variables scoped implicitly by the OpenMP specification, such as loop index variables of worksharing **DO** or **FOR** loops.

3.2.1 Scoping Rules For Scalar Variables

- **S1:** If the use of the variable in the parallel region is free of *data race*¹ conditions for the threads in the team executing the region, then the variable is scoped **SHARED**.

1. A *data race* exists when two threads can access the same shared variable at the same time with at least one thread modifying the variable. To remove a data race condition, put the accesses in a critical section or synchronize the threads.

- **S2:** If in each thread executing the parallel region, the variable is always written before being read by the same thread, then the variable is scoped **PRIVATE**. The variable is scoped as **LASTPRIVATE** if it can be scoped **PRIVATE** and is read before it is written after the parallel region, and the construct is either a **PARALLEL DO** or a **PARALLEL SECTIONS**.
- **S3:** If the variable is used in a reduction operation that can be recognized by the compiler, then the variable is scoped **REDUCTION** with that particular operation type.

3.2.2 Scoping Rules for Arrays

- **A1:** If the use of the array in the parallel region is free of data race conditions for the threads in the team executing the region, then the array is scoped as **SHARED**.

3.3 General Comments About Autoscopying

When autoscopying a variable that does not have implicit scope, the compiler checks the use of the variable against the rules in the given order. If a rule matches, the compiler will scope the variable according to the matching rule. If a rule does not match, the compiler tries the next rule. If the compiler is unable to find a match, the compiler gives up attempting to determine the scope of that variable and it is scoped **SHARED** and the binding parallel region is serialized as if an **IF (.FALSE.)** or **if(0)** clause were specified.

There are two reasons why autoscopying fails. One is that the use of the variable does not match any of the rules. The other is that the source code is too complex for the compiler to do a sufficient analysis. Function calls, complicated array subscripts, memory aliasing, and user-implemented synchronization are some typical causes. (See [Section 3.5, “Known Limitations of the Current Implementation”](#) on page 3-9.)

3.3.1 Autoscopying Rules for Fortran 95:

For Fortran, specifying the following kinds of variables to be autoscoped by an **__AUTO** or **DEFAULT(__AUTO)** directive causes the compiler to scope the variable according to the implicit scoping rules in the OpenMP specification:

- A **THREADPRIVATE** variable
- A Cray *pointee*.
- A loop iteration variable used only in sequential loops in the lexical extent of the region or worksharing DO loops that bind to the region.

- Implied **DO** or **FORALL** indices.
- Variables that are used only in work-sharing constructs that bind to the region, and are specified in a data scope attribute clause for each such construct.

3.3.2 Autoscoping Rules for C/C++:

For C/C++, if a user specifies the following variables to be autoscoped by a **__auto** or **default(__auto)** pragma, the compiler will scope the variable according to the implicit scoping rules of the OpenMP Specification:

- The variable is declared within the parallel construct.
- The variable has **THREADPRIVATE** attribute.
- The variable has a const-qualified type.
- The variable is the loop control variable for a **for** loop that immediately follows a **for** or **parallel for** pragma, and the variable reference appears inside the loop.

Autoscopying in C and C++ applies only to basic data types: integer, floating point, and pointer. If a user specified a structure variable or class variable to be autoscoped, the compiler will scope the variable as **shared** and the enclosing parallel region will be executed by a single thread.

3.4 Checking the Results of Autoscopying

Use *compiler commentary* to check autoscopying results and to see if any parallel regions are serialized because autoscopying failed.

The compiler will produce an inline commentary when compiled with the `-g` debug option. This generated commentary can be viewed with the `er_src` command, as shown in [CODE EXAMPLE 3-2](#). (The `er_src` command is provided as part of the Sun Studio software; for more information, see the `er_src(1)` man page or the *Sun Studio Performance Analyzer* manual.)

A good place to start is to compile with the `-xvpara` option. A warning message will be printed out if autoscopying fails, as shown in [CODE EXAMPLE 3-1](#).

CODE EXAMPLE 3-1 Compiling With `-vpara`

```
>cat t.f
      INTEGER X(100), Y(100), I, T
C$OMP PARALLEL DO DEFAULT(__AUTO)
      DO I=1, 100
          T = Y(I)
          CALL FOO(X)
          X(I) = T*T
      END DO
C$OMP END PARALLEL DO
      END
>f95 -xopenmp -xO3 -vpara -c t.f
"t.f", line 3: Warning: parallel region is serialized
      because the autoscopying of following variables failed
      - x
```

Compile with `-vpara` with `f95`, `-xvpara` with `cc`. (This option has not yet been implemented in `CC`.)

CODE EXAMPLE 3-2 Using Compiler Commentary

```
>cat t.f
    INTEGER X(100), Y(100), I, T
C$OMP PARALLEL DO DEFAULT(__AUTO)
    DO I=1, 100
        T = Y(I)
        X(I) = T*T
    END DO
C$OMP END PARALLEL DO
END

>f95 -xopenmp -xO3 -g -c t.f
>er_src omp_t.o
Source file: ./omp_t.f
Object file: ./omp_t.o
Load Object: ./omp_t.o

1.      INTEGER X(100), Y(100), I, T
      <Function: MAIN_>

Source OpenMP region below has tag R1
Variables autoscoped as PRIVATE in R1: t, i
Variables autoscoped as SHARED in R1: x, y
Private variables in R1: i, t
Shared variables in R1: y, x
2. C$OMP PARALLEL DO DEFAULT(__AUTO)

Source loop below has tag L1
Source loop below has tag L1
L1 parallelized by explicit user directive
Discovered loop below has tag L2
L-unknown scheduled with steady-state cycle count = 3
L-unknown unrolled 4 times
L-unknown has 0 loads, 0 stores, 2 prefetches, 0 FPadds, 0 FPMuls, and 0
FPdivs per iteration
L-unknown has 1 int-loads, 1 int-stores, 4 alu-ops, 1 muls, 0 int-divs and
1 shifts per iteration
3.      DO I=1, 100
4.          T = Y(I)
5.          X(I) = T*T
6.      END DO
7. C$OMP END PARALLEL DO
8.      END
```

Next, a more complicated example to illustrate how the autoscoping rules work.

CODE EXAMPLE 3-3 A More Complicated Example

```
1.      REAL FUNCTION FOO (N, X, Y)
2.      INTEGER      N, I
3.      REAL         X(*), Y(*)
4.      REAL         W, MM, M
5.
6.      W = 0.0
7.
8.      C$OMP PARALLEL DEFAULT(__AUTO)
9.
10.     C$OMP SINGLE
11.         M = 0.0
12.     C$OMP END SINGLE
13.
14.         MM = 0.0
15.
16.     C$OMP DO
17.         DO I = 1, N
18.             T = X(I)
19.             Y(I) = T
20.             IF (MM .GT. T) THEN
21.                 W = W + T
22.                 MM = T
23.             END IF
24.         END DO
25.     C$OMP END DO
26.
27.     C$OMP CRITICAL
28.         IF ( MM .GT. M ) THEN
29.             M = MM
30.         END IF
31.     C$OMP END CRITICAL
32.
33.     C$OMP END PARALLEL
34.
35.         FOO = W - M
36.
37.         RETURN
38.     END
```

The function **FOO()** contains a parallel region, which contains a **SINGLE** construct, a work-sharing **DO** construct and a **CRITICAL** construct. If we ignore all the OpenMP parallel constructs, what the code in the parallel region does is:

1. Copy the value in array **X** to array **Y**
2. Find the maximum positive value in **X**, and store it in **M**
3. Accumulate the value of some elements of **X** into variable **W**.

Let's see how the compiler uses the above rules to find the appropriate scopes for the variables in the parallel region.

The following variables are used in the parallel region, **I**, **N**, **MM**, **T**, **W**, **M**, **X**, and **Y**. The compiler will determine the following.

- Scalar **I** is the loop index of the work-sharing **DO** loop. The OpenMP specification mandates that **I** be scoped **PRIVATE**.
- Scalar **N** is only read in the parallel region and therefore will not cause data race, so it is scoped as **SHARED** following rule **S1**.
- Any thread executing the parallel region will execute statement 14, which sets the value of scalar **MM** to 0.0. This write will cause data race, so rule **S1** does not apply. The write happens before any read of **MM** in the same thread, so **MM** is scoped as **PRIVATE** according to rule **S2**.
- Similarly, scalar **T** is scoped as **PRIVATE**.
- Scalar **W** is read and then written at statement 21, so rules **S1** and **S2** do not apply. The addition operation is both associative and communicative, therefore, **W** is scoped as **REDUCTION(+)** according to rule **S3**.
- Scalar **M** is written in statement 11 which is inside a **SINGLE** construct. The implicit barrier at the end of the **SINGLE** construct ensures that the write in statement 11 will not happen concurrently with either the read in statement 28 or the write in statement 29, and the latter two will not happen at the same time because both are inside the same **CRITICAL** construct. No two threads can access **M** at the same time. Therefore, the writes and reads of **M** in the parallel region do not cause a data race, and, following rule **S1**, **M** is scoped **SHARED**.
- Array **X** is only read and not written in the region, so it is scoped as **SHARED** by rule **A1**.
- The writes to array **Y** is distributed among the threads, and no two threads will write to the same elements of **Y**. As there is no data race, **Y** is scoped **SHARED** according to rule **A1**.

3.5 Known Limitations of the Current Implementation

Here are the known limitations to autoscoping in the current Sun Studio Fortran 95 compiler.

- Only OpenMP directives are recognized and used in the analysis. Calls to OpenMP runtime routines are not recognized. For example, if a program uses `OMP_SET_LOCK()` and `OMP_UNSET_LOCK()` to implement a critical section, the compiler is not able to detect the existence of the critical section. Use **CRITICAL** and **END CRITICAL** directives if possible.
- Only synchronizations specified by using OpenMP synchronization directives, such as **BARRIER** and **MASTER**, are recognized and used in the analysis. User-implemented synchronizations, such as busy-waiting, are not recognized.
- Autoscoping is not supported when compiling with `-xopenmp=noopt`.

Implementation-Defined Behaviors

This chapter notes specific behaviors in the OpenMP 2.5 specification that are implementation dependent. For last-minute information regarding the latest compiler releases, see the compiler documentation on the Sun Developer Network portal, <http://developers.sun.com/sunstudio>

■ Memory Model

There is no guarantee that memory accesses by multiple threads to the same variable *without synchronization* are atomic with respect to each other.

Several implementation-dependent and application-dependent factors affect whether accesses are atomic or not. Some variables might be larger than the largest atomic memory operation on the target platform. Some variables might be mis-aligned or of unknown alignment and the compiler or the run-time system may need to use multiple loads/stores to access the variable. Sometimes there are faster code sequences that use more loads/stores.

■ Internal Control Variables

The OpenMP runtime library maintains the following internal control variables:

nthreads-var - stores the number of threads requested for future parallel regions.

dyn-var - controls whether dynamic adjustment of the number of threads to be used for future parallel regions is enabled.

nest-var - controls whether nested parallelism is enabled for future parallel regions.

run-sched-var - stores scheduling information to be used for loop regions using the **RUNTIME** schedule clause.

def-sched-var - stores implementation defined default scheduling information for loop regions.

The runtime library maintains separate copies of each of *nthreads-var*, *dyn-var*, and *nest-var* for each thread. On the other hand, the runtime library maintains one copy of each of *run-sched-var* and *def-sched-var* that applies to all threads.

■ Number of Threads

The default value of *nthreads-var* is 1. That is, without an explicit **num_threads()** clause, a call to the **omp_set_num_threads()** routine, or an explicit definition of the **OMP_NUM_THREADS** environment variable, the default number of threads in a team is 1.

A call to **omp_set_num_threads()** modifies the value of *nthreads-var* for the calling thread only and applies to parallel regions at the same or inner nesting level encountered by the calling thread.

If the requested number of threads is greater than the number of threads an implementation can support or if the value is not a positive integer, then if **SUNW_MP_WARN** is set to **TRUE** or a callback function is registered by a call to **sunw_mp_register_warn()**, a warning message will be issued.

■ Nested Parallelism

Nested parallelism is supported. Nested parallel regions can be executed by multiple threads.

The default value of *nest-var* is *false*. That is, nested parallelism is disabled by default. Set the **OMP_NESTED** environment variable, or call the **omp_set_nested()** routine to enable it.

A call to **omp_set_nested()** modifies the value of *nest-var* for the calling thread only and applies to parallel regions at the same or inner nesting level encountered by the calling thread.

By default, the maximum number of active nesting levels supported is 4. You can change that maximum by setting the environment variable **SUNW_MP_MAX_NESTED_LEVELS**.

■ Dynamic Adjustment of Threads

The default value of *dyn-var* is *true*. That is, dynamic adjustment is enabled by default. Set the **OMP_DYNAMIC** environment variable, or call the **omp_set_dynamic()** routine to disable dynamic adjustment.

A call to **omp_set_dynamic()** modifies the value of *dyn-var* for the calling thread only and applies to parallel regions at the same or inner nesting level encountered by the calling thread.

If dynamic adjustment is enabled, then the number of threads in the team is adjusted to be the minimum of:

- the number of threads the user requested
- 1 + the number of available threads in the pool
- the number of available processors

On the other hand, if dynamic adjustment is disabled, then the number of threads in the team will be the minimum of:

- the number of threads the user requested
- 1 + the number of available threads in the pool

In exceptional situations, such as when there is lack of system resources, the number of threads supplied will be less than described above. In these situations, if `SUNW_MP_WARN` is set to `TRUE` or a callback function is registered via a call to `sunw_mp_register_warn()`, a warning message will be issued.

Refer to Chapter 2 for more information about the pool of threads and the nested parallelism execution model.

■ Loop Scheduling

The default value of *def-sched-var* is `STATIC` scheduling. To specify a different schedule for a loop region, use the `SCHEDULE` clause.

The default value of *run-sched-var* is also `STATIC` scheduling. You can change the default by setting the `OMP_SCHEDULE` environment variable

■ GUIDED: Determination of Chunk Sizes

The default chunk size for `SCHEDULE (GUIDED)` when *chunksize* is not specified is 1. The OpenMP runtime library uses the following formula for computing the chunk sizes for a loop with `GUIDED` scheduling:

$$\text{chunksize} = \text{unassigned_iterations} / (\text{weight} * \text{num_threads})$$

where:

unassigned_iterations is the number of iterations in the loop that have not yet been assigned to any thread;

weight is a floating-point constant that can be specified by the user at runtime with the `SUNW_MP_GUIDED_WEIGHT` environment variable (Section 5.3, “OpenMP Environment Variables” on page 5-5). The current default, if not specified, assumes *weight* is 2.0;

num_threads is the number of threads used to execute the loop.

Choice of the weight value affects the sizes of the initial and subsequent chunks of iterations assigned to threads in loops, and has a direct affect on load balancing. Experimental results show that the default weight of 2.0 works well generally. However some applications could benefit from a different weight value.

■ Explicitly Threaded Programs

Programs that are explicitly threaded using POSIX or Solaris threads can contain OpenMP directives or call routines that contain OpenMP directives.

■ Runtime Warnings

- Setting the **SUNW_MP_WARN** environment variable ([Section 5.3, “OpenMP Environment Variables” on page 5-5](#)) enables runtime validity checking by the OpenMP runtime library.

For example, the following code will fall into an endless loop as threads wait at different barriers, and must be terminated with a control-C from the terminal:

```
% cat bad1.c

#include <omp.h>
#include <stdio.h>

int
main(void)
{
    omp_set_dynamic(0);
    omp_set_num_threads(4);

    #pragma omp parallel
    {
        int i = omp_get_thread_num();

        if (i % 2) {
            printf("At barrier 1.\n");
            #pragma omp barrier
        }
    }
    return 0;
}
% cc -xopenmp -xO3 bad1.c
% ./a.out          run the program
At barrier 1.
At barrier 1.
                                program hung in endless loop
Control-C to terminate execution
```

But if we set **SUNW_MP_WARN** before execution, the runtime library will detect the problem:

```
% setenv SUNW_MP_WARN TRUE
% ./a.out
At barrier 1.
At barrier 1.
WARNING (libmtnsk): Threads at barrier from different directives.
  Thread at barrier from bad1.c:11.
  Thread at barrier from bad1.c:17.
Possible Reasons:
Worksharing constructs not encountered by all threads in the team in the
same order.
Incorrect placement of barrier directives.
```

- The C and C++ compilers also provide a function that can be used to register a callback function when errors are detected. When an error is detected, the registered callback function is called and passed a pointer to an error message string as an argument.

```
int sunw_mp_register_warn(void (*func) (void *) )
```

Access to the prototype for this function requires adding
`#include <sunw_mp_misc.h>`

For example:

```
% cat bad2.c
#include <omp.h>
#include <sunw_mp_misc.h>
#include <stdio.h>

void handle_warn(void *msg)
{
    printf("handle_warn: %s\n", (char *)msg);
}

void set(int i)
{
    static int k;
#pragma omp critical
    {
        k++;
    }
#pragma omp barrier
}

int main(void)
{
    int i, rc;
    omp_set_dynamic(0);
    omp_set_num_threads(4);
    if (sunw_mp_register_warn(handle_warn) != 0) {
        printf ("Installing callback failed\n");
    }
#pragma omp parallel for
    for (i = 0; i < 20; i++) {
        set(i);
    }
    return 0;
}

% cc -xopenmp -xO3 bad2.c
% a.out
handle_warn: WARNING (libmstk): at bad2.c:21 Barrier is not permitted
in dynamic extent of for / DO.
```

`handle_warn()` is installed as the callback function when an error is detected by the OpenMP runtime library. The callback function in this example merely prints the error message passed to it from the library, but could be used to trap certain errors.

- **Regarding Specific Constructs:**

- sections** construct

- The structured blocks in a **sections** construct are divided among the members of the team executing the sections region, so that the threads execute an approximately equal number of sections.

- single** construct

- The structured block of a **single** construct will be executed by the thread that encounters the single region first.

- atomic** construct

- This implementation replaces all **ATOMIC** directives and pragmas by enclosing the target statement in a **CRITICAL** construct.

- **Binding Thread Set for OpenMP Library Routines:**

- omp_set_num_threads** routine

- When called from within an explicit parallel region, the binding thread set for the `omp_set_num_threads` region is the calling thread.

- omp_get_max_threads** routine

- When called from within an explicit parallel region, the binding thread set for the `omp_get_max_threads` region is the calling thread.

- omp_set_dynamic** routine

- When called from within any explicit parallel region, the binding thread set for the `omp_set_dynamic` region is the calling thread only.

- omp_get_dynamic** routine

- When called from within an explicit parallel region, the binding thread set for the `omp_get_dynamic` region is the calling thread only.

- omp_set_nested** routine

- When called from within an explicit parallel region, the binding thread set for the `omp_set_nested` region is the calling thread only.

- omp_get_nested** routine

- When called from within an explicit parallel region, the binding thread set for the `omp_get_nested` region is the calling thread only.

- **Fortran 95-Specific Issues:**

- threadprivate** directive

- If the conditions for values of data in the `threadprivate` objects of threads (other than the initial thread) to persist between two consecutive active parallel regions do not all hold, then the allocation status of an allocatable array in the second region may be "not currently allocated".

shared clause

Passing a shared variable to a non-intrinsic procedure may result in the value of the shared variable being copied into temporary storage before the procedure reference, and back out of the temporary storage into the actual argument storage after the procedure reference. This copying into and out of temporary storage can occur only if conditions a, b, and c in Section 2.8.3.2 of the OpenMP 2.5 Specification hold.

Include and module files

Both the include file `omp_lib.h` and the module file `omp_lib` are provided in this implementation.

The OpenMP runtime library routines that take an argument are extended with a generic interface so arguments of different Fortran `KIND` type can be accommodated.

Compiling for OpenMP

This chapter describes how to compile programs that utilize the OpenMP API.

To run a parallelized program in a multithreaded environment, you must set the **OMP_NUM_THREADS** environment variable prior to program execution. This tells the runtime system the maximum number of threads the program can create. The default is 1. In general, set **OMP_NUM_THREADS** to a value no larger than the available number of processors on the target platform. Set **OMP_DYNAMIC** to **FALSE** to use the number of threads specified by **OMP_NUM_THREADS**.

The latest information regarding Sun Studio compilers and OpenMP can be found on the Sun Developer Network portal,
<http://developers.sun.com/sunstudio>

5.1 Compiler Options To Use

To enable explicit parallelization with OpenMP directives, compile your program with the **cc**, **CC**, or **f95** option flag **-xopenmp**. This flag can take an optional keyword argument. (The **f95** compiler accepts both **-xopenmp** and **-openmp** as synonyms.)

The **-xopenmp** flag accepts the following keyword sub-options.

-xopenmp=parallel	Enables recognition of OpenMP pragmas. The minimum optimization level for -xopenmp=parallel is -xO3 . The compiler changes the optimization from a lower level to -xO3 if necessary, and issues a warning.
-xopenmp=noopt	Enables recognition of OpenMP pragmas. The compiler does not raise the optimization level if it is lower than -xO3 . If you explicitly set the optimization level lower than -xO3 , as in -xO2 -openmp=noopt the compiler will issue an error. If you do not specify an optimization level with -openmp=noopt , the OpenMP pragmas are recognized, the program is parallelized accordingly, but no optimization is done. (This sub-option applies to cc and f95 only; CC issues a warning if specified, and no OpenMP parallelization is done.)
-xopenmp=stubs	This option is no longer supported. An OpenMP stubs library is provided for users' convenience. To compile an OpenMP program that calls OpenMP library routines but ignores the OpenMP pragmas, compile the program without an -xopenmp option, and link the object files with the libompstubs.a library. For example, <pre>% cc omp_ignore.c -lompstubs</pre> Linking with both libompstubs.a and the OpenMP runtime library libmstk.so is unsupported and may result in unexpected behavior.
-xopenmp=none	Disables recognition of OpenMP pragmas and does not change the optimization level.

Additional Notes:

- If you do not specify **-xopenmp** on the command line, the compiler assumes **-xopenmp=none** (disabling recognition of OpenMP pragmas).
- If you specify **-xopenmp** but without a keyword sub-option, the compiler assumes **-xopenmp=parallel**.
- Do not specify **-xopenmp** together with **-xparallel** or **-xexplicitpar** on the command line.
- Specifying **-xopenmp=parallel** or **noopt** will define the **_OPENMP** preprocessor token to be **YYYYMM** (specifically **200505L** for C/C++ and **200505** for Fortran 95).
- When debugging OpenMP programs with **dbx**, compile with **-xopenmp=noopt -g**

- The default optimization level for **-xopenmp** might change in future releases. Compilation warning messages can be avoided by specifying an appropriate optimization level explicitly.
- With Fortran 95, **-xopenmp** , **-xopenmp=parallel**, **-xopenmp=noopt** will add **-stackvar** automatically.
- If you compile with **-xopenmp** when building a dynamic (**.so**) library, you must also specify **-xopenmp** when linking the executable, and the compiler used to create the executable must be at least as new as the compiler that built the dynamic library with **-xopenmp**. Using different compiler versions with **-xopenmp** to create the executable and the library, can result in unexpected behavior.
- Use the **-xvpara** C and Fortran 95 option to display compiler parallelization messages.

5.2 Fortran 95 OpenMP Validation

You can obtain a static, interprocedural validation of a Fortran 95 program's OpenMP directives by using the **f95** compiler's global program checking feature. Enable OpenMP checking by compiling with the **-xlistMP** flag. (Diagnostic messages from **-xlistMP** appear in a separate file created with the name of the source file and a **.lst** extension). The compiler will diagnose the following violations and parallelization inhibitors:

- Violations in the specifications of parallel directives, including improper nesting.
- Parallelization inhibitors due to data usage, detected by interprocedural dependence analysis.
- Parallelization inhibitors detected by interprocedural pointer analysis.

For example, compiling a source file `ord.f` with `-xlistMP` produces a diagnostic file `ord.lst`:

```
FILE "ord.f"
 1  !$OMP PARALLEL
 2  !$OMP DO ORDERED
 3          do i=1,100
 4              call work(i)
 5          end do
 6  !$OMP END DO
 7  !$OMP END PARALLEL
 8
 9  !$OMP PARALLEL
10  !$OMP DO
11          do i=1,100
12              call work(i)
13          end do
14  !$OMP END DO
15  !$OMP END PARALLEL
16          end
17          subroutine work(k)
18  !$OMP ORDERED
    ^
**** ERR-OMP: It is illegal for an ORDERED directive to bind to a
directive (ord.f, line 10, column 2) that does not have the
ORDERED clause specified.
19          write(*,*) k
20  !$OMP END ORDERED
21          return
22          end
```

In this example, the **ORDERED** directive in subroutine **WORK** receives a diagnostic that refers to the second **DO** directive because it lacks an **ORDERED** clause.

5.3 OpenMP Environment Variables

The OpenMP specification defines four environment variables that control the execution of OpenMP programs. These are summarized in the following table.

TABLE 5-1 OpenMP Environment Variables

Environment Variable	Function
OMP_SCHEDULE	Sets schedule type for DO , PARALLEL DO , for , parallel for , directives/pragmas with schedule type RUNTIME specified. If not defined, a default value of STATIC is used. <i>value</i> is " <i>type[,chunk]</i> " Example: <code>setenv OMP_SCHEDULE "GUIDED,4"</code>
OMP_NUM_THREADS or PARALLEL	Sets the number of threads to use during execution of a parallel region. You can override this value by a NUM_THREADS clause, or a call to OMP_SET_NUM_THREADS() . If not set, a default of 1 is used. <i>value</i> is a positive integer. For compatibility with legacy programs, setting the PARALLEL environment variable has the same effect as setting OMP_NUM_THREADS . However, if they are both set to different values, the runtime library will issue an error message. Example: <code>setenv OMP_NUM_THREADS 16</code>
OMP_DYNAMIC	Enables or disables dynamic adjustment of the number of threads available for execution of parallel regions. If not set, a default value of TRUE is used. <i>value</i> is either TRUE or FALSE . Example: <code>setenv OMP_DYNAMIC FALSE</code>
OMP_NESTED	Enables or disables nested parallelism. <i>value</i> is either TRUE or FALSE . The default is FALSE . Example: <code>setenv OMP_NESTED FALSE</code>

Additional multiprocessing environment variables affect execution of OpenMP programs and are not part of the OpenMP specifications. These are summarized in the following table.

TABLE 5-2 Multiprocessing Environment Variables

Environment Variable	Function
SUNW_MP_WARN	<p>Controls warning messages issued by the OpenMP runtime library. If set to TRUE the runtime library issues warning messages to <code>stderr</code>; FALSE disables warning messages. The default is FALSE.</p> <p>The OpenMP runtime library has the ability to check for many common OpenMP violations, such as incorrect nesting and deadlocks. Runtime checking does add overhead to the execution of the program. See “Runtime Warnings” on page 4-4.</p> <p>Example:</p> <pre>setenv SUNW_MP_WARN TRUE</pre>
SUNW_MP_THR_IDLE	<p>Controls the end-of-task status of each helper thread executing the parallel part of a program. You can set the value to SPIN, SLEEP <i>ns</i>, or SLEEP <i>nms</i>. The default is SLEEP — the thread sleeps after completing a parallel task until a new parallel task arrives.</p> <p>Choosing SLEEP <i>time</i> specifies the amount of time a helper thread should spin-wait after completing a parallel task. If, while a thread is spinning, a new task arrives for the thread, the thread executes the new task immediately. Otherwise, the thread goes to sleep and is awakened when a new task arrives. <i>time</i> may be specified in seconds, (<i>ns</i>) or just (<i>n</i>), or milliseconds, (<i>nms</i>).</p> <p>SLEEP with no argument puts the thread to sleep immediately after completing a parallel task. SLEEP, SLEEP (0), SLEEP (0s), and SLEEP (0ms) are all equivalent.</p> <p>Example:</p> <pre>setenv SUNW_MP_THR_IDLE SLEEP(50ms)</pre>
SUNW_MP_PROCBIND	<p>The SUNW_MP_PROCBIND environment variable can be used to bind threads of an OpenMP program to processors. Performance can be enhanced with processor binding, but performance degradation will occur if multiple threads are bound to the same processor. See Section 5.4, “Processor Binding” on page 5-8 for details.</p>

TABLE 5-2 Multiprocessing Environment Variables (*Continued*)

Environment Variable	Function
SUNW_MP_MAX_POOL_THREADS	Specifies the maximum size of the thread pool. The thread pool contains only non-user threads that the OpenMP runtime library creates. It does not contain the master thread or any threads created explicitly by the user's program. If this environment variable is set to zero, the thread pool will be empty and all parallel regions will be executed by one thread. The default, if not specified, is 1023. See Section 2.2, "Control of Nested Parallelism" on page 2-2 for details.
SUNW_MP_MAX_NESTED_LEVELS	Specifies the maximum depth of active nested parallel regions. Any parallel region that has an active nested depth greater than the value of this environment variable will be executed by only one thread. A parallel region is considered not active if it is an OpenMP parallel region that has a false IF clause. The default, if not specified, is 4. See Section 2.2, "Control of Nested Parallelism" on page 2-2 for details.
STACKSIZE	Sets the stack size for each thread. The value is in kilobytes. The default thread stack sizes are 4 Mb on 32-bit SPARC V8 and x86 platforms, and 8 Mb on 64-bit SPARC V9 and x86 platforms. Example: setenv STACKSIZE 8192 <i>sets the thread stack size to 8 Mb</i> The STACKSIZE environment variable also accepts numerical values with a suffix of either B , K , M , or G for bytes, kilobytes, megabytes, or gigabytes respectively. The default is kilobytes.
SUNW_MP_GUIDED_WEIGHT	Sets the weighting factor used to determine the size of chunks assigned to threads in loops with GUIDED scheduling. The value should be a positive floating-point number, and will apply to all loops with GUIDED scheduling in the program. If not set, the default value assumed is 2.0.

5.4 Processor Binding

With processor binding, the programmer instructs the Operating System (Solaris) that a thread in the program should run on the same processor throughout the execution of the program.

Processor binding, when used along with static scheduling, benefits applications that exhibit a certain data reuse pattern where data accessed by a thread in a parallel or worksharing region will be in the local cache from a previous invocation of a parallel or worksharing region.

From the hardware point of view, a computer system is composed of one or more *physical* processors. From the Operating System (Solaris) point of view, each of these *physical* processors maps to one or more *virtual* processors onto which threads in a program can be run. For example, each UltraSPARC IV physical processor has two cores. From the Solaris OS point of view, each of these cores is a *virtual* processor onto which a thread can be scheduled to run.

When the operating system binds threads to processors, they are in effect bound to specific *virtual* processors, not *physical* processors.

To bind threads in an OpenMP program to specific virtual processors, set the **SUNW_MP_PROCBIND** environment variable. The value specified for **SUNW_MP_PROCBIND** can be one of the following:

- The string **"TRUE"** or **"FALSE"** (or lower case **"true"** or **"false"**). For example,
`% setenv SUNW_MP_PROCBIND "false"`
- A non-negative integer. For example,
`% setenv SUNW_MP_PROCBIND "2"`
- A list of two or more non-negative integers separated by one or more spaces. For example,
`% setenv SUNW_MP_PROCBIND "0 2 4 6"`
- Two non-negative integers, $n1$ and $n2$, separated by a minus ("-"); $n1$ must be less than or equal to $n2$. For example,
`% setenv SUNW_MP_PROCBIND "0-6"`

Note that the non-negative integers referred to above denote logical identifiers (IDs). Logical IDs may be different from *virtual* processor IDs. The difference will be explained below.

Virtual Processor IDs:

Each virtual processor in a system has a unique processor ID. You can use the Solaris OS `psrinfo(1M)` command to display information about the processors in a system, including their processor IDs. Moreover, you can use the `prtdiag(1M)` command to display system configuration and diagnostic information.

On later Solaris releases, you can use `psrinfo -pv` to list all physical processors in the system and the virtual processors that are associated with each physical processor.

Virtual processor IDs may be sequential or there may be gaps in the IDs. For example, on a Sun Fire 4810 with 8 UltraSPARC IV processors (16 cores), the virtual processor IDs may be: 0, 1, 2, 3, 8, 9, 10, 11 512, 513, 514, 515, 520, 521, 522, 523.

Logical IDs:

As mentioned above, the non-negative integers specified for `SUNW_MP_PROCBIND` are logical IDs. Logical IDs are consecutive integers that start with 0. If the number of virtual processors available in the system is n , then their logical IDs are 0, 1, ..., $n-1$, in the order presented by `psrinfo(1M)`. The following Korn shell script can be used to display the mapping from virtual processor IDs to logical IDs.

```
#!/bin/ksh

NUMV=`psrinfo | fgrep "on-line" | wc -l`
set -A VID `psrinfo | cut -f1`

echo "Total number of on-line virtual processors = $NUMV"
echo

let "I=0"
let "J=0"
while [[ $I -lt $NUMV ]]
do
    echo "Virtual processor ID ${VID[I]} maps to logical ID ${J}"
    let "I=I+1"
    let "J=J+1"
done
```

On systems where a single physical processor maps to several virtual processors, it may be useful to know which logical IDs correspond to virtual processors that belong to the same physical processor. The following Korn shell script can be used with later Solaris releases to display this information.

```
#!/bin/ksh

NUMV=`psrinfo | grep "on-line" | wc -l`
set -A VLIST `psrinfo | cut -f1`
set -A CHECKLIST `psrinfo | cut -f1`

let "I=0"

while [ $I -lt $NUMV ]
do
  let "COUNT=0"
  SAMELIST="$I"

  let "J=I+1"

  while [ $J -lt $NUMV ]
  do
    if [ ${CHECKLIST[J]} -ne -1 ]
    then
      if [ `psrinfo -p ${VLIST[I]} ${VLIST[J]} ` = 1 ]
      then
        SAMELIST="$SAMELIST $J"
        let "CHECKLIST[J]=-1"
        let "COUNT=COUNT+1"
      fi
    fi
    let "J=J+1"
  done

  if [ $COUNT -gt 0 ]
  then
    echo "The following logical IDs belong to the same physical
processor:"
    echo "$SAMELIST"
    echo " "
  fi

  let "I=I+1"
done
```

Interpreting the Value Specified for `SUNW_MP_PROCBIND`:

If the value specified for `SUNW_MP_PROCBIND` is a non-negative integer, then that integer denotes the starting logical ID of the virtual processor to which threads should be bound. Threads will be bound to virtual processors in a round-robin fashion, starting with the processor with the specified logical ID, and wrapping around to the processor with logical ID 0, after binding to the processor with logical ID $n-1$. If the value specified for `SUNW_MP_PROCBIND` is a list of two or more non-negative integers, then threads will be bound in a round-robin fashion to virtual processors with the specified logical IDs. Processors with logical IDs other than those specified will not be used.

If the value specified for `SUNW_MP_PROCBIND` is two non-negative integers separated by a minus ("-"), then threads will be bound in a round-robin fashion to virtual processors in the range that begins with the first logical ID and ends with the second logical ID. Processors with logical IDs other than those included in the range will not be used.

If the value specified for `SUNW_MP_PROCBIND` does not conform to one of the forms described above, or if an invalid logical ID is given, then an error message will be emitted and execution of the program will terminate.

Note that the number of threads created by the microtasking library, `libmtsk`, depends on environment variables, API calls in the user's program, and the `num_threads` clause. `SUNW_MP_PROCBIND` specifies the logical IDs of virtual processors to which the threads should be bound. Threads will be bound to that set of processors in a round-robin fashion. If the number of threads used in the program is less than the number of logical IDs specified by `SUNW_MP_PROCBIND`, then some virtual processors will not be used by the program. If the number of threads is greater than the number of logical IDs specified by `SUNW_MP_PROCBIND`, then some virtual processors will have more than one thread bound to them.

5.5 Stacks and Stack Sizes

The executing program maintains a main memory stack for the initial thread executing the program, as well as distinct stacks for each slave thread. Stacks are temporary memory address spaces used to hold arguments and automatic variables during invocation of a subprogram or function reference.

In general, the default main stack size is 8 megabytes. Compiling Fortran programs with the `£95 -stackvar` option forces the allocation of local variables and arrays on the stack as if they were automatic variables. Use of `-stackvar` with OpenMP programs is implied with explicitly parallelized programs because it improves the

optimizer's ability to parallelize calls in loops. (See the *Fortran User's Guide* for a discussion of the **-stackvar** flag.) However, this may lead to stack overflow if not enough memory is allocated for the stack.

Use the **limit** C-shell command, or the **ulimit** ksh/sh command, to display or set the size of the main stack.

Each slave thread of an OpenMP program has its own thread stack. This stack mimics the initial (or main) thread stack but is unique to the thread. The thread's **PRIVATE** arrays and variables (local to the thread) are allocated on the thread stack. The default size is 4 megabytes on 32-bit SPARC V8 and x86 platforms, and 8 megabytes on 64-bit SPARC V9 and x86 platforms. The size of the helper thread stack is set with the **STACKSIZE** environment variable.

```
demo% setenv STACKSIZE 16384    <-Set thread stack size to 16 Mb (C shell)
demo$ STACKSIZE=16384          <-Same, using Bourne/Korn shell
demo$ export STACKSIZE
```

Finding the best stack size might have to be determined by trial and error. If the stack size is too small for a thread to run it may cause silent data corruption in neighboring threads, or segmentation faults. If you are unsure about stack overflows, compile your Fortran, C, or C++ programs with the **-xcheck=stkovf** flag to force a segmentation fault on stack overflow. This stops the program before any data corruption can occur.

Converting to OpenMP

This chapter gives guidelines for converting legacy programs using Sun or Cray directives and pragmas to OpenMP.

Note – Legacy Sun and Cray parallelization directives are now deprecated and no longer supported by Sun Studio compilers.

6.1 Converting Legacy Fortran Directives

Legacy Fortran programs use either Sun or Cray style parallelization directives. A description of these directives can be found in the chapter *Parallelization* in the *Fortran Programming Guide*.

6.1.1 Converting Sun-Style Fortran Directives

The following tables give OpenMP near equivalents to Sun parallelization directives and their subclauses. These are only suggestions.

TABLE 6-1 Converting Sun Parallelization Directives to OpenMP

Sun Directive	Equivalent OpenMP Directive
C\$PAR DOALL [<i>qualifiers</i>]	!\$omp parallel do [<i>qualifiers</i>]
C\$PAR DOSERIAL	No exact equivalent. You can use: !\$omp master <i>loop</i> !\$omp end master
C\$PAR DOSERIAL*	No exact equivalent. You can use: !\$omp master <i>loopnest</i> !\$omp end master
C\$PAR TASKCOMMON <i>block[,...]</i>	!\$omp threadprivate (/block/[...])

The DOALL directive can take the following optional qualifier clauses.

TABLE 6-2 DOALL Qualifier Clauses and OpenMP Equivalent Clauses

Sun DOALL Clause	OpenMP PARALLEL DO Equivalent Clauses
PRIVATE (<i>v1,v2,...</i>)	private (<i>v1,v2,...</i>)
SHARED (<i>v1,v2,...</i>)	shared (<i>v1,v2,...</i>)
MAXCPUS (<i>n</i>)	num_threads (<i>n</i>) . No exact equivalent.
READONLY (<i>v1,v2,...</i>)	No exact equivalent. You can achieve the same effect by using firstprivate (<i>v1,v2,...</i>) .
STOREBACK (<i>v1,v2,...</i>)	lastprivate (<i>v1,v2,...</i>) .
SAVELAST	No exact equivalent. You can achieve the same effect by using lastprivate (<i>v1,v2,...</i>) .
REDUCTION (<i>v1,v2,...</i>)	reduction (operator : <i>v1,v2,...</i>) Must supply the reduction operator as well as the list of variables.
SCHEDTYPE (<i>spec</i>)	schedule (<i>spec</i>) (See TABLE 6-3)

The SCHEDTYPE (*spec*) clause accepts the following scheduling specifications.

TABLE 6-3 SCHEDTYPE Scheduling and OpenMP schedule Equivalents

SCHEDTYPE(<i>spec</i>)	OpenMP <code>schedule(spec)</code> Clause Equivalent
SCHEDTYPE (STATIC)	<code>schedule (static)</code>
SCHEDTYPE (SELF (<i>chunksize</i>))	<code>schedule (dynamic, chunksize)</code> Default <i>chunksize</i> is 1.
SCHEDTYPE (FACTORING (<i>m</i>))	No exact equivalent.
SCHEDTYPE (GSS (<i>m</i>))	<code>schedule (guided, m)</code> Default <i>m</i> is 1.

6.1.1.1 Issues Between Sun-Style Fortran Directives and OpenMP

- Scoping of private variables must be declared explicitly with OpenMP. With Sun directives, the compiler uses its own default scoping rules for variables not explicitly scoped in a **PRIVATE** or **SHARED** clause: all scalars are treated as **PRIVATE**, and all array references are **SHARED**. With OpenMP, the default data scope is **SHARED** unless a **DEFAULT (PRIVATE)** clause appears on the **PARALLEL DO** directive. A **DEFAULT (NONE)** clause causes the compiler to flag variables not scoped explicitly. However, see [Chapter 3](#) for information on autoscoping in Fortran.
- Since there is no **DOSERIAL** directive, mixing automatic and explicit OpenMP parallelization may have different effects: some loops may be automatically parallelized that would not have been with Sun directives.
- OpenMP provides a richer parallelism model by providing parallel regions and parallel sections. It could be possible to get better performance by redesigning the parallelism strategies of a program that uses Sun directives to take advantage of these features of OpenMP.

6.1.2 Converting Cray-Style Fortran Directives

Cray-style Fortran parallelization directives are identical to Sun-style except that the sentinel that identifies these directives is **!MIC\$**. Also, the set of qualifier clauses on the **!MIC\$ DOALL** is different.

TABLE 6-4 OpenMP Equivalents for Cray-Style DOALL Qualifier Clauses

Cray DOALL Clause	OpenMP PARALLEL DO Equivalent Clauses
SHARED (<i>v1,v2,...</i>)	SHARED (<i>v1,v2,...</i>)
PRIVATE (<i>v1,v2,...</i>)	PRIVATE (<i>v1,v2,...</i>)
AUTOSCOPE	No equivalent. Scoping must be explicit, or with the DEFAULT clause, or with the __AUTO clause
SAVELAST	No exact equivalent. You can achieve the same effect by using <code>lastprivate</code> .
MAXCPUS (<i>n</i>)	<code>num_threads(<i>n</i>)</code> . No exact equivalent.
GUIDED	<code>schedule(guided, <i>m</i>)</code> Default <i>m</i> is 1.
SINGLE	<code>schedule(dynamic, 1)</code>
CHUNKSIZE (<i>n</i>)	<code>schedule(dynamic, <i>n</i>)</code>
NUMCHUNKS (<i>m</i>)	<code>schedule(dynamic, <i>n/m</i>)</code> where <i>n</i> is the number of iterations

6.1.2.1 Issues Between Cray-Style Fortran Directives and OpenMP Directives

The differences are the same as for Sun-style directives, except that there is no equivalent for the Cray **AUTOSCOPE**.

6.2 Converting Legacy C Pragmas

The C compiler accepts legacy pragmas for explicit parallelization. These are described in the *C User's Guide*. As with the Fortran directives, these are only suggestions.

The legacy parallelization pragmas are:

TABLE 6-5 Converting Legacy C Parallelization Pragmas to OpenMP

Legacy C Pragma	Equivalent OpenMP Pragma
#pragma MP taskloop [clauses]	#pragma omp parallel for [clauses]
#pragma MP serial_loop	No exact equivalent. You can use #pragma omp master loop
#pragma MP serial_loop_nested	No exact equivalent. You can use #pragma omp master loopnest

The taskloop pragma can take on one or more of the following optional clauses.

TABLE 6-6 taskloop Optional Clauses and OpenMP Equivalents

taskloop Clause	OpenMP parallel for Equivalent Clause
maxcpus (<i>n</i>)	No exact equivalent. Use num_threads (<i>n</i>)
private (<i>v1,v2,...</i>)	private (<i>v1,v2,...</i>)
shared (<i>v1,v2,...</i>)	shared (<i>v1,v2,...</i>)
readonly (<i>v1,v2,...</i>)	No exact equivalent. You can achieve the same effect by using firstprivate (<i>v1,v2,...</i>).
storeback (<i>v1,v2,...</i>)	You can achieve the same effect by using lastprivate (<i>v1,v2,...</i>).
savelast	No exact equivalent. You can achieve the same effect by using lastprivate (<i>v1,v2,...</i>).
reduction (<i>v1,v2,...</i>)	reduction (operator: <i>v1,v2,...</i>). Must supply the reduction operator as well as the list of variables.
schedtype (<i>spec</i>)	schedule (<i>spec</i>) (See TABLE 6-7)

The `schedtype(spec)` clause accepts the following scheduling specifications.

TABLE 6-7 SCHEDTYPE Scheduling and OpenMP schedule Equivalents

schedtype(spec)	OpenMP schedule(spec) Clause Equivalent
SCHEDTYPE (STATIC)	<code>schedule(static)</code>
SCHEDTYPE (SELF (<i>chunksize</i>))	<code>schedule(dynamic, chunksize)</code> Note: Default <i>chunksize</i> is 1.
SCHEDTYPE (FACTORING (<i>m</i>))	No exact equivalent.
SCHEDTYPE (GSS (<i>m</i>))	<code>schedule(guided, m)</code> Default <i>m</i> is 1.

6.2.1 Issues Between Legacy C Pragmas and OpenMP

- OpenMP scopes variables declared within a parallel construct as **private**. A **default(none)** clause on a **#pragma omp parallel** for directive causes the compiler to flag variables not scoped explicitly.
- Since there is no **serial_loop** directive, mixing automatic and explicit OpenMP parallelization may have different effects: some loops may be automatically parallelized that would not have been with legacy C directives.
- Because OpenMP provides a richer parallelism model, it is often possible to get better performance by redesigning the parallelism strategies of a program that uses legacy C directives to take advantage of these features.

Performance Considerations

Once you have a correct, working OpenMP program, it is worth considering its overall performance. There are some general techniques that you can utilize to improve the efficiency and scalability of an OpenMP application, as well as techniques specific to the Sun platforms. These are discussed briefly here.

For additional information, see *Techniques for Optimizing Applications: High Performance Computing*, by Rajat Garg and Ilya Sharapov, which is available from <http://www.sun.com/books/catalog/garg.xml>

Also, visit the Sun Developer portal for occasional articles and case studies regarding performance analysis and optimization of OpenMP applications, at <http://developers.sun.com/prodtech/cc/>.

7.1 Some General Recommendations

The following are some general techniques for improving performance of OpenMP applications.

- Minimize synchronization.
 - Avoid or minimize the use of **BARRIER**, **CRITICAL** sections, **ORDERED** regions, and locks.
 - Use the **NOWAIT** clause where possible to eliminate redundant or unnecessary barriers. For example, there is always an implied barrier at the end of a parallel region. Adding **NOWAIT** to a final **DO** in the region eliminates one redundant barrier.
 - Use named **CRITICAL** sections for fine-grained locking.
 - Use explicit **FLUSH** with care. Flushes can cause data cache restores to memory, and subsequent data accesses may require reloads from memory, all of which decrease efficiency.

- By default, idle threads will be put to sleep after a certain time out period. It could be that the default time out period is not sufficient for your application, causing the threads to go to sleep too soon or too late. The **SUNW_MP_THR_IDLE** environment variable can be used to override the default time out period, even up to the point where the idle threads will never be put to sleep and remain active all the time.
- Parallelize at the highest level possible, such as outer **DO/FOR** loops. Enclose multiple loops in one parallel region. In general, make parallel regions as large as possible to reduce parallelization overhead. For example:

This construct is less efficient:

```
!$OMP PARALLEL
  ....
  !$OMP DO
    ....
  !$OMP END DO
  ....
!$OMP END PARALLEL

!$OMP PARALLEL
  ....
  !$OMP DO
    ....
  !$OMP END DO
  ....
!$OMP END PARALLEL
```

than this one:

```
!$OMP PARALLEL
  ....
  !$OMP DO
    ....
  !$OMP END DO
  ....

  !$OMP DO
    ....
  !$OMP END DO

!$OMP END PARALLEL
```

- Use **PARALLEL DO/FOR** instead of worksharing **DO/FOR** directives in parallel regions. The **PARALLEL DO/FOR** is implemented more efficiently than a general parallel region containing possibly several loops. For example:

This construct is less efficient:

```
!$OMP PARALLEL
!$OMP DO
    . . . . .
!$OMP END DO
!$OMP END PARALLEL
```

than this one:

```
!$OMP PARALLEL DO
    . . . . .
!$OMP END PARALLEL
```

- Use **SUNW_MP_PROCBIND** to bind threads to processors. Processor binding, when used along with static scheduling, benefits applications that exhibit a certain data reuse pattern where data accessed by a thread in a parallel region will be in the local cache from a previous invocation of a parallel region. See [Section 5.4, “Processor Binding” on page 5-8](#).
- Use **MASTER** instead of **SINGLE** wherever possible.
 - The **MASTER** directive is implemented as an **IF**-statement with no implicit **BARRIER** :


```
IF(omp_get_thread_num() == 0) {...}
```
 - The **SINGLE** directive is implemented similar to other worksharing constructs. Keeping track of which thread reached **SINGLE** first adds additional runtime overhead. There is an implicit **BARRIER** if **NOWAIT** is not specified. It is less efficient.
- Choose the appropriate loop scheduling.
 - **STATIC** causes no synchronization overhead and can maintain data locality when data fits in cache. However, **STATIC** may lead to load imbalance.
 - **DYNAMIC, GUIDED** incurs a synchronization overhead to keep track of which chunks have been assigned. And, while these schedules could lead to poor data locality, they can improve load balancing. Experiment with different chunk sizes.

- Use **LASTPRIVATE** with care, as it has the potential of high overhead.
 - Data needs to be copied from private to shared storage upon return from the parallel construct.
 - The compiled code checks which thread executes the logically last iteration. This imposes extra work at the end of each chunk in a parallel **DO/FOR**. The overhead adds up if there are many chunks.
- Use efficient thread-safe memory management.
 - Applications could be using **malloc()** and **free()** explicitly, or implicitly in the compiler-generated code for dynamic/allocatable arrays, vectorized intrinsics, and so on.
 - The thread-safe **malloc()** and **free()** in **libc** have a high synchronization overhead caused by internal locking. Faster versions can be found in the **libmtmalloc** library. Link with **-lmtmalloc** to use **libmtmalloc**.
- Small data cases may cause OpenMP parallel loops to underperform. Use the **IF** clause on **PARALLEL** constructs to indicate that a loop should run parallel only in those cases where some performance gain can be expected.
- When possible, merge loops. For example:

```

merge two loops
!$omp parallel do
  do i = ...
    statements_1
  end do
!$omp parallel do
  do i = ...
    statements_2
  end do

into a single loop
!$omp parallel do
  do i = ...
    statements_1
    statements_2
  end do

```

- Try nested parallelism if your application lacks scalability beyond a certain level. See [Chapter 2](#) for more information about nested parallelism in OpenMP.

7.2 False Sharing And How To Avoid It

Careless use of shared memory structures with OpenMP applications can result in poor performance and limited scalability. Multiple processors updating adjacent shared data in memory can result in excessive traffic on the multiprocessor interconnect and, in effect, cause serialization of computations.

7.2.1 What Is *False Sharing*?

Most high performance processors, such as UltraSPARC processors, insert a cache buffer between slow memory and the high speed registers of the CPU. Accessing a memory location causes a slice of actual memory (a *cache line*) containing the memory location requested to be copied into the cache. Subsequent references to the same memory location or those around it can probably be satisfied out of the cache until the system determines it is necessary to maintain the coherency between cache and memory.

However, simultaneous updates of individual elements in the same cache line coming from different processors invalidates entire cache lines, even though these updates are logically independent of each other. Each update of an individual element of a cache line marks the line as *invalid*. Other processors accessing a different element in the same line see the line marked as *invalid*. They are forced to fetch a more recent copy of the line from memory or elsewhere, even though the element accessed has not been modified. This is because cache coherency is maintained on a cache-line basis, and not for individual elements. As a result there will be an increase in interconnect traffic and overhead. Also, while the cache-line update is in progress, access to the elements in the line is inhibited.

This situation is called *false sharing*. If this occurs frequently, performance and scalability of an OpenMP application will suffer significantly.

False sharing degrades performance when all of the following conditions occur.

- Shared data is modified by multiple processors.
- Multiple processors update data within the same cache line.
- This updating occurs very frequently (for example, in a tight loop).

Note that shared data that is read-only in a loop does not lead to false sharing.

7.2.2 Reducing False Sharing

Careful analysis of those parallel loops that play a major part in the execution of an application can reveal performance scalability problems caused by false sharing. In general, false sharing can be reduced by

- making use of private data as much as possible;
- utilizing the compiler's optimization features to eliminate memory loads and stores.

In specific cases, the impact of false sharing may be less visible when dealing with larger problem sizes, as there might be less sharing.

Techniques for tackling false sharing are very much dependent on the particular application. In some cases, a change in the way the data is allocated can reduce false sharing. In other cases, changing the mapping of iterations to threads, giving each thread more work per chunk (by changing the *chunksize* value) can also lead to a reduction in false sharing.

7.3 Operating System Tuning Features

Starting with the Solaris 9 release, the operating system provides scalability and high performance for the SunFire™ systems. New features introduced with Solaris 9 OS that improve the performance of OpenMP programs without hardware upgrades are Memory Placement Optimizations (MPO) and Multiple Page Size Support (MPSS), among others.

MPO allows the OS to allocate pages close to the processors that access those pages. SunFire E20K, and SunFire E25K systems have different memory latencies within the same UniBoard™ versus between different UniBoards. The default MPO policy, called *first-touch*, allocates memory on the UniBoard containing the processor that first touches the memory. The first-touch policy can greatly improve the performance of applications where data accesses are made mostly to the memory local to each processor with first-touch placement. Compared to a random memory placement policy where the memory is evenly distributed throughout the system, the memory latencies for applications can be lowered and the bandwidth increased, leading to higher performance.

The MPSS feature is supported as of the Solaris 9 OS release, and allows a program to use different page sizes for different regions of virtual memory. The default Solaris page size is relatively small (8KB on UltraSPARC processors and 4KB on AMD64 Opteron processors). Applications that suffer from too many TLB misses may experience a performance boost by using a larger page size.

TLB misses can be measured using the Sun Performance Analyzer.

The default page size on a specific platform can be obtained with the Solaris OS command: `/usr/bin/pagesize`. The `-a` option on this command lists all the supported page sizes. (See the `pagesize(1)` man page for details.)

There are three ways to change the default page size for an application:

- Use the Solaris OS command `ppgsz(1)`
- Compile the application with the `-xpagesize`, `-xpagesize_heap`, and `-xpagesize_stack` options. (See the compiler man pages for details.)
- Use MPSS specific environment variables. See the `mpss.so.1(1)` man page for details.

Placement of Clauses on Directives

The following table relates clauses to directives and pragmas:

TABLE A-1 Pragmas Where Clauses Can Appear

Clause/Pragma	PARALLEL	DO/for	SECTIONS	SINGLE	PARALLEL DO/for	PARALLEL SECTIONS	PARALLEL WORKSHARE ³
IF	•				•	•	•
PRIVATE	•	•	•	•	•	•	•
SHARED	•				•	•	•
FIRSTPRIVATE	•	•	•	•	•	•	•
LASTPRIVATE		•	•		•	•	
DEFAULT	•				•	•	•
REDUCTION	•	•	•		•	•	•
COPYIN	•				•	•	•
COPYPRIVATE				• ¹			
ORDERED		•			•		
SCHEDULE		•			•		
NOWAIT		• ²	• ²	• ²			
NUM_THREADS	•				•	•	•
_AUTO	•				•	•	•

1. Fortran only: **COPYPRIVATE** can appear on the **END SINGLE** directive.
2. For Fortran, a **NOWAIT** modifier can only appear on the **END DO**, **END SECTIONS**, **END SINGLE**, or **END WORKSHARE** directives.
3. Only Fortran supports **WORKSHARE** and **PARALLEL WORKSHARE**.

Index

Symbols

`__AUTO`, 3-2

A

accessible documentation, -xvi
automatic scoping, 3-1
autoscopying rules, 3-3

C

cache line, 7-5
compilers, accessing, -xi
compiling for OpenMP, 5-1
converting to OpenMP
 Cray-style Fortran directives, 6-4
 legacy C pragmas, 6-4
 Sun-style Fortran directives, 6-2

D

directive
 See pragma
directives
 validation (Fortran 95), 5-3
documentation index, -xv
documentation, accessing, -xv to -xvii
dynamic thread adjustment, 5-5
dynamic threads, 4-2

E

environment variables, 5-5
explicitly threaded programs, 4-3

F

false sharing, 7-5

G

guided scheduling, 5-7
guided weight, 4-3

I

idle threads, 5-6
implementation, 4-1

M

man pages, accessing, -xi
MANPATH environment variable, setting, -xiii
memory placement optimization (MPO), 7-6

N

nested parallelism, 2-1, 2-2, 4-2, 5-5
number of threads, 4-2
 OMP_NUM_THREADS, 5-5

O

OMP_DYNAMIC, 5-5
OMP_NESTED, 2-2, 5-5
OMP_NUM_THREADS, 5-5
OMP_SCHEDULE, 5-5
OpenMP API specification, 1-1

P

parallelism, nested, 2-1
PATH environment variable, setting, -xii

performance, 7-1
platforms, supported, -x
pragma
 See directive

R

runtime checking, 4-4

S

scalability, 7-5
scheduling, 4-3
 OMP_SCHEDULE, 5-5
scheduling clauses
 SCHEDULE, 4-3
scoping of variables
 automatic, 3-1
 autoscoping limitations, 3-9
 compiler commentary, 3-5
 rules, 3-2
shell prompts, -x
SLEEP, 5-6
Solaris OS tuning, 7-6
SPIN, 5-6
stack size, 5-7, 5-11
stacks, 5-11
STACKSIZE, 5-7
-stackvar, 5-11
SUNW_MP_GUIDED_WEIGHT, 4-3, 5-7
SUNW_MP_MAX_NESTED_LEVELS, 2-4, 5-7
SUNW_MP_MAX_POOL_THREADS, 2-3, 5-7
sunw_mp_misc.h, 4-5
SUNW_MP_PROCBIND, 5-6
sunw_mp_register_warn(), 4-5
SUNW_MP_THR_IDLE, 5-6
SUNW_MP_WARN, 4-4, 5-6
supported platforms, -x

T

thread stack size, 5-7
typographic conventions, -ix

V

validation of directives (Fortran 95), 5-3

W

warning messages, 5-6
weighting factor, 4-3, 5-7

X

-xlistMP, 5-3
-xopenmp, 5-1