

Sun GlassFish Enterprise Server v2.1.1 Administration Reference



Sun Microsystems, Inc.
4150 Network Circle
Santa Clara, CA 95054
U.S.A.

Part No: 821-0183-10
October 2009

Copyright 2009 Sun Microsystems, Inc. 4150 Network Circle, Santa Clara, CA 95054 U.S.A. All rights reserved.

Sun Microsystems, Inc. has intellectual property rights relating to technology embodied in the product that is described in this document. In particular, and without limitation, these intellectual property rights may include one or more U.S. patents or pending patent applications in the U.S. and in other countries.

U.S. Government Rights – Commercial software. Government users are subject to the Sun Microsystems, Inc. standard license agreement and applicable provisions of the FAR and its supplements.

This distribution may include materials developed by third parties.

Parts of the product may be derived from Berkeley BSD systems, licensed from the University of California. UNIX is a registered trademark in the U.S. and other countries, exclusively licensed through X/Open Company, Ltd.

Sun, Sun Microsystems, the Sun logo, the Solaris logo, the Java Coffee Cup logo, docs.sun.com, Java, and Solaris are trademarks or registered trademarks of Sun Microsystems, Inc. or its subsidiaries in the U.S. and other countries. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. in the U.S. and other countries. Products bearing SPARC trademarks are based upon an architecture developed by Sun Microsystems, Inc.

The OPEN LOOK and SunTM Graphical User Interface was developed by Sun Microsystems, Inc. for its users and licensees. Sun acknowledges the pioneering efforts of Xerox in researching and developing the concept of visual or graphical user interfaces for the computer industry. Sun holds a non-exclusive license from Xerox to the Xerox Graphical User Interface, which license also covers Sun's licensees who implement OPEN LOOK GUIs and otherwise comply with Sun's written license agreements.

Products covered by and information contained in this publication are controlled by U.S. Export Control laws and may be subject to the export or import laws in other countries. Nuclear, missile, chemical or biological weapons or nuclear maritime end uses or end users, whether direct or indirect, are strictly prohibited. Export or reexport to countries subject to U.S. embargo or to entities identified on U.S. export exclusion lists, including, but not limited to, the denied persons and specially designated nationals lists is strictly prohibited.

DOCUMENTATION IS PROVIDED "AS IS" AND ALL EXPRESS OR IMPLIED CONDITIONS, REPRESENTATIONS AND WARRANTIES, INCLUDING ANY IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE OR NON-INFRINGEMENT, ARE DISCLAIMED, EXCEPT TO THE EXTENT THAT SUCH DISCLAIMERS ARE HELD TO BE LEGALLY INVALID.

Copyright 2009 Sun Microsystems, Inc. 4150 Network Circle, Santa Clara, CA 95054 U.S.A. Tous droits réservés.

Sun Microsystems, Inc. détient les droits de propriété intellectuelle relatifs à la technologie incorporée dans le produit qui est décrit dans ce document. En particulier, et ce sans limitation, ces droits de propriété intellectuelle peuvent inclure un ou plusieurs brevets américains ou des applications de brevet en attente aux États-Unis et dans d'autres pays.

Cette distribution peut comprendre des composants développés par des tierces personnes.

Certaines composants de ce produit peuvent être dérivées du logiciel Berkeley BSD, licenciés par l'Université de Californie. UNIX est une marque déposée aux Etats-Unis et dans d'autres pays; elle est licenciée exclusivement par X/Open Company, Ltd.

Sun, Sun Microsystems, le logo Sun, le logo Solaris, le logo Java Coffee Cup, docs.sun.com, Java et Solaris sont des marques de fabrique ou des marques déposées de Sun Microsystems, Inc., ou ses filiales, aux Etats-Unis et dans d'autres pays. Toutes les marques SPARC sont utilisées sous licence et sont des marques de fabrique ou des marques déposées de SPARC International, Inc. aux Etats-Unis et dans d'autres pays. Les produits portant les marques SPARC sont basés sur une architecture développée par Sun Microsystems, Inc.

L'interface d'utilisation graphique OPEN LOOK et Sun a été développée par Sun Microsystems, Inc. pour ses utilisateurs et licenciés. Sun reconnaît les efforts de pionniers de Xerox pour la recherche et le développement du concept des interfaces d'utilisation visuelle ou graphique pour l'industrie de l'informatique. Sun détient une licence non exclusive de Xerox sur l'interface d'utilisation graphique Xerox, cette licence couvrant également les licenciés de Sun qui mettent en place l'interface d'utilisation graphique OPEN LOOK et qui, en outre, se conforment aux licences écrites de Sun.

Les produits qui font l'objet de cette publication et les informations qu'il contient sont régis par la législation américaine en matière de contrôle des exportations et peuvent être soumis au droit d'autres pays dans le domaine des exportations et importations. Les utilisations finales, ou utilisateurs finaux, pour des armes nucléaires, des missiles, des armes chimiques ou biologiques ou pour le nucléaire maritime, directement ou indirectement, sont strictement interdites. Les exportations ou réexportations vers des pays sous embargo des Etats-Unis, ou vers des entités figurant sur les listes d'exclusion d'exportation américaines, y compris, mais de manière non exclusive, la liste de personnes qui font l'objet d'un ordre de ne pas participer, d'une façon directe ou indirecte, aux exportations des produits ou des services qui sont régis par la législation américaine en matière de contrôle des exportations et la liste de ressortissants spécifiquement désignés, sont rigoureusement interdites.

LA DOCUMENTATION EST FOURNIE "EN L'ETAT" ET TOUTES AUTRES CONDITIONS, DECLARATIONS ET GARANTIES EXPRESSES OU TACITES SONT FORMELLEMENT EXCLUES, DANS LA MESURE AUTORISEE PAR LA LOI APPLICABLE, Y COMPRIS NOTAMMENT TOUTE GARANTIE IMPLICITE RELATIVE A LA QUALITE MARCHANDE, A L'APTITUDE A UNE UTILISATION PARTICULIERE OU A L'ABSENCE DE CONTREFACON.

Contents

Preface	9
1 The domain.xml File	15
About the domain.xml File	15
The sun-domain_1_5.dtd File	16
Default Values	16
Variables	16
Element Referencing	18
Element Hierarchy	18
Alphabetical List of Elements	21
A	22
access-log	22
action	23
admin-object-resource	23
admin-service	24
alert-service	25
alert-subscription	26
appclient-module	26
application-ref	27
applications	28
audit-module	29
auth-realm	29
availability-service	32
B	35
backend-principal	35
C	36
cluster	36
cluster-ref	38

clusters	39
config	40
configs	41
connection-pool	42
connector-connection-pool	42
connector-module	46
connector-resource	47
connector-service	48
custom-resource	49
D	50
das-config	50
description	51
diagnostic-service	52
domain	53
E	54
ejb-container	54
ejb-container-availability	56
ejb-module	57
ejb-timer-service	59
event	59
extension-module	64
external-jndi-resource	65
F	66
filter-config	66
G	67
group-management-service	67
H	68
health-checker	68
http-access-log	69
http-file-cache	70
http-listener	71
http-protocol	75
http-service	76
I	79
iiop-listener	79
iiop-service	80

J	81
j2ee-application	81
jacc-provider	82
java-config	83
jdbc-connection-pool	85
jdbc-resource	89
jms-availability	90
jms-host	91
jms-service	92
jmx-connector	94
jvm-options	96
K	96
keep-alive	96
L	97
lb-config	97
lb-configs	98
lifecycle-module	98
listener-config	99
load-balancer	100
load-balancers	102
log-service	102
M	104
mail-resource	104
management-rule	106
management-rules	107
manager-properties	108
mbean	109
mdb-container	110
message-security-config	111
module-log-levels	112
module-monitoring-levels	114
monitoring-service	115
N	115
node-agent	115
node-agents	116
O	117

orb	117
overload-protection-service	118
P	119
persistence-manager-factory-resource	119
principal	120
profiler	121
property	121
provider-config	123
R	125
registry-location	125
request-policy	125
request-processing	126
resource-adapter-config	126
resource-ref	127
resources	128
response-policy	129
S	130
security-map	130
security-service	131
server	132
server-ref	133
servers	134
session-config	135
session-manager	135
session-properties	136
ssl	137
ssl-client-config	138
store-properties	139
system-property	139
T	141
thread-pool	141
thread-pools	142
transaction-service	142
transformation-rule	145
U	146
user-group	146

V	146
virtual-server	146
W	151
web-container	151
web-container-availability	152
web-module	155
web-service-endpoint	157
Index	159

Preface

This *Administration Reference* provides information about the Sun GlassFish Enterprise Server configuration file, `domain.xml`. This file contains most of the Enterprise Server configuration.

This preface contains information about and conventions for the entire Sun GlassFish™ Enterprise Server documentation set.

Enterprise Server Documentation Set

The Uniform Resource Locator (URL) for Enterprise Server documentation is <http://docs.sun.com/coll/1343.11>. For an introduction to Enterprise Server, refer to the books in the order in which they are listed in the following table.

TABLE P–1 Books in the Enterprise Server Documentation Set

Book Title	Description
<i>Documentation Center</i>	Enterprise Server documentation topics organized by task and subject.
<i>Release Notes</i>	Late-breaking information about the software and the documentation. Includes a comprehensive, table-based summary of the supported hardware, operating system, Java™ Development Kit (JDK™), and database drivers.
<i>Quick Start Guide</i>	How to get started with the Enterprise Server product.
<i>Installation Guide</i>	Installing the software and its components.
<i>Application Deployment Guide</i>	Deployment of applications and application components to the Enterprise Server. Includes information about deployment descriptors.
<i>Developer's Guide</i>	Creating and implementing Java Platform, Enterprise Edition (Java EE platform) applications intended to run on the Enterprise Server that follow the open Java standards model for Java EE components and APIs. Includes information about developer tools, security, debugging, and creating lifecycle modules.
<i>Java EE 5 Tutorial</i>	Using Java EE 5 platform technologies and APIs to develop Java EE applications.

TABLE P-1 Books in the Enterprise Server Documentation Set *(Continued)*

Book Title	Description
<i>Java WSIT Tutorial</i>	Developing web applications using the Web Service Interoperability Technologies (WSIT). Describes how, when, and why to use the WSIT technologies and the features and options that each technology supports.
<i>Administration Guide</i>	System administration for the Enterprise Server, including configuration, monitoring, security, resource management, and web services management.
<i>High Availability Administration Guide</i>	Setting up clusters, working with node agents, and using load balancers.
<i>Administration Reference</i>	Editing the Enterprise Server configuration file, <code>domain.xml</code> .
<i>Performance Tuning Guide</i>	Tuning the Enterprise Server to improve performance.
<i>Reference Manual</i>	Utility commands available with the Enterprise Server; written in man page style. Includes the <code>asadmin</code> command line interface.

Related Documentation

For documentation about other stand-alone Sun GlassFish server products, go to the following:

- [Message Queue documentation \(`http://docs.sun.com/coll/1343.4`\)](http://docs.sun.com/coll/1343.4)
- [Identity Server documentation \(`http://docs.sun.com/app/docs/prod/ident.mgmt#hic`\)](http://docs.sun.com/app/docs/prod/ident.mgmt#hic)
- [Directory Server documentation \(`http://docs.sun.com/coll/1224.1`\)](http://docs.sun.com/coll/1224.1)
- [Web Server documentation \(`http://docs.sun.com/coll/1308.3`\)](http://docs.sun.com/coll/1308.3)

A Javadoc™ tool reference for packages provided with the Enterprise Server is located at <http://glassfish.dev.java.net/nonav/javaee5/api/index.html>. Additionally, the following resources might be useful:

- [The Java EE 5 Specifications \(`http://java.sun.com/javaee/5/javatech.html`\)](http://java.sun.com/javaee/5/javatech.html)
- [The Java EE Blueprints \(`http://java.sun.com/reference/blueprints/index.html`\)](http://java.sun.com/reference/blueprints/index.html)

For information on creating enterprise applications in the NetBeans™ Integrated Development Environment (IDE), see <http://www.netbeans.org/kb/55/index.html>.

For information about the Java DB database included with the Enterprise Server, see <http://developers.sun.com/javadb/>.

The GlassFish Samples project is a collection of sample applications that demonstrate a broad range of Java EE technologies. The GlassFish Samples are bundled with the Java EE Software Development Kit (SDK), and are also available from the GlassFish Samples project page at <https://glassfish-samples.dev.java.net/>.

Default Paths and File Names

The following table describes the default paths and file names that are used in this book.

TABLE P–2 Default Paths and File Names

Placeholder	Description	Default Value
<i>as-install</i>	Represents the base installation directory for Enterprise Server.	Solaris™ and Linux installations, non-root user: <i>user's home-directory/SUNWappserver</i> Solaris and Linux installations, root user: <i>/opt/SUNWappserver</i> Windows, all installations: <i>SystemDrive:\Sun\AppServer</i>
<i>domain-root-dir</i>	Represents the directory containing all domains.	All installations: <i>as-install/domains/</i>
<i>domain-dir</i>	Represents the directory for a domain. In configuration files, you might see <i>domain-dir</i> represented as follows: <code> \${com.sun.aas.instanceRoot}</code>	<i>domain-root-dir/domain-dir</i>
<i>instance-dir</i>	Represents the directory for a server instance.	<i>domain-dir/instance-dir</i>
<i>samples-dir</i>	Represents the directory containing sample applications.	<i>as-install/samples</i>
<i>docs-dir</i>	Represents the directory containing documentation.	<i>as-install/docs</i>

Typographic Conventions

The following table describes the typographic changes that are used in this book.

TABLE P–3 Typographic Conventions

Typeface	Meaning	Example
AaBbCc123	The names of commands, files, and directories, and onscreen computer output	Edit your <code>.login</code> file. Use <code>ls -a</code> to list all files. <code>machine_name% you have mail.</code>

TABLE P-3 Typographic Conventions *(Continued)*

Typeface	Meaning	Example
AaBbCc123	What you type, contrasted with onscreen computer output	<code>machine_name% su Password:</code>
<i>AaBbCc123</i>	A placeholder to be replaced with a real name or value	The command to remove a file is <code>rm filename</code> .
<i>AaBbCc123</i>	Book titles, new terms, and terms to be emphasized (note that some emphasized items appear bold online)	Read Chapter 6 in the <i>User's Guide</i> . A <i>cache</i> is a copy that is stored locally. Do <i>not</i> save the file.

Symbol Conventions

The following table explains symbols that might be used in this book.

TABLE P-4 Symbol Conventions

Symbol	Description	Example	Meaning
[]	Contains optional arguments and command options.	<code>ls [-l]</code>	The <code>-l</code> option is not required.
{ }	Contains a set of choices for a required command option.	<code>-d {y n}</code>	The <code>-d</code> option requires that you use either the <code>y</code> argument or the <code>n</code> argument.
`\${ }`	Indicates a variable reference.	<code> \${com.sun.javaRoot}</code>	References the value of the <code>com.sun.javaRoot</code> variable.
-	Joins simultaneous multiple keystrokes.	Control-A	Press the Control key while you press the A key.
+	Joins consecutive multiple keystrokes.	Ctrl+A+N	Press the Control key, release it, and then press the subsequent keys.
→	Indicates menu item selection in a graphical user interface.	File → New → Templates	From the File menu, choose New. From the New submenu, choose Templates.

Documentation, Support, and Training

The Sun web site provides information about the following additional resources:

- Documentation (<http://www.sun.com/documentation/>)
- Support (<http://www.sun.com/support/>)
- Training (<http://www.sun.com/training/>)

Third-Party Web Site References

Third-party URLs are referenced in this document and provide additional, related information.

Note – Sun is not responsible for the availability of third-party web sites mentioned in this document. Sun does not endorse and is not responsible or liable for any content, advertising, products, or other materials that are available on or through such sites or resources. Sun will not be responsible or liable for any actual or alleged damage or loss caused or alleged to be caused by or in connection with use of or reliance on any such content, goods, or services that are available on or through such sites or resources.

Sun Welcomes Your Comments

Sun is interested in improving its documentation and welcomes your comments and suggestions.

To share your comments, go to <http://docs.sun.com> and click Feedback. In the online form, provide the document title and part number. The part number is a seven-digit or nine-digit number that can be found on the title page of the book or at the top of the document.

The domain.xml File

This chapter describes the `domain.xml` configuration file in these sections:

- “[About the domain.xml File](#)” on page 15
- “[Alphabetical List of Elements](#)” on page 21

Note – Subelements must be defined in the order in which they are listed under each **Subelements** heading in this chapter unless otherwise noted.

About the domain.xml File

The `domain.xml` file contains most of the Sun Java™ System Enterprise Server configuration. The encoding is UTF-8 to maintain compatibility with regular UNIX text editors. The `domain.xml` file is located in the domain configuration directory, which is typically `domain-dir/config`. This file is further described in the following sections:

- “[The sun-domain_1_5.dtd File](#)” on page 16
- “[Default Values](#)” on page 16
- “[Variables](#)” on page 16
- “[Element Referencing](#)” on page 18
- “[Element Hierarchy](#)” on page 18

Note – Settings in the Enterprise Server deployment descriptors override corresponding settings in the `domain.xml` file unless otherwise stated. For more information about the Enterprise Server deployment descriptors, see the [*Sun GlassFish Enterprise Server v2.1.1 Application Deployment Guide*](#).

The sun-domain_1_5.dtd File

The sun-domain_1_5.dtd file defines the structure of the domain.xml file, including the elements it can contain and the subelements and attributes these elements can have. The sun-domain_1_5.dtd file is located in the *as-install/lib/dtds* directory.

Note – Do not edit the sun-domain_1_5.dtd file; its contents change only with new versions of the Enterprise Server.

The sun-domain_1_5.dtd interface is unstable. An unstable interface might be experimental or transitional, and hence might change incompatibly, be removed, or be replaced by a more stable interface in the next release.

Elements or attributes that appear in the sun-domain_1_5.dtd file but are not described in this chapter are not implemented and should not be used.

For general information about DTD files and XML, see the [XML specification](http://www.w3.org/TR/REC-xml) (<http://www.w3.org/TR/REC-xml>).

Default Values

In this manual, the term *default* is used in its broader sense, and not in the specific way it is used in the XML 1.0 standard. A default value is an initial value or the value used if no value is present in the XML file. A default value can be any of the following:

- A value supplied by the XML parser when no value is found in the domain.xml file. The relevant element or attribute is optional.
- A value supplied by the Enterprise Server when no value is found in the domain.xml file and the XML parser doesn't provide a value. The relevant element or attribute is optional.
- An initial value supplied when the domain.xml file is created. The relevant element or attribute might or might not be optional.

When a required attribute or property has a default, this default is supplied when the domain.xml file is created.

Variables

Variables and variable references are needed for two reasons:

- Parts of the Enterprise Server share much configuration information but differ in specific details. For example, server instances in a cluster typically share the same configuration except for their port numbers.

- Parts of the configuration come from the system environment but must still be captured in the configuration.

Variable references appear in the `domain.xml` file as strings that begin with the characters \${ and end with the character }. For example, the string \${com.sun.enterprise.myVar} is a reference to the variable `com.sun.enterprise.myVar`.

Variables are defined both outside of and within `domain.xml`. Predefined variables that exist outside of `domain.xml` are defined as Java System Properties. Within `domain.xml`, a variable is defined using the “[system-property](#)” on page 139 element or the “[jvm-options](#)” on page 96 element.

The `system-property` element’s `name` attribute is the name of a variable; its `value` attribute is the definition of the variable. For example, the following `system-property` element defines a `port-number` variable with the value `6500`:

```
<system-property name="port-number" value="6500"/>
```

Multiple `system-property` subelements are permitted within “[server](#)” on page 132, “[cluster](#)” on page 36, “[config](#)” on page 40, and “[domain](#)” on page 53 elements.

A variable defined in the `jvm-options` element is a Java System Property with the -D flag. For example, the following `jvm-options` element defines a `port-number` variable with the value `5500`:

```
<jvm-option>-Dport-number=5500</jvm-option>
```

Multiple definitions for the same variable are permitted. The Enterprise Server determines the actual value of a variable by searching for its first definition in a strict hierarchy of the elements within `domain.xml`. The hierarchy is as follows:

server → cluster → config → jvm-options → domain → System

Implicit in this hierarchy is the notion of reference and containment. A variable referenced in a `server` element is only looked up:

- In the `cluster` element referenced by that specific `server`
- In the `config` element that references that specific `server`
- In the `jvm-options` subelements of the `config` element referenced by that `server`

Note – Some topics in the documentation pertain to features that are available only in domains that are configured to support clusters. Examples of domains that support clusters are domains that are created with the cluster profile or the enterprise profile. For information about profiles, see “[Usage Profiles](#)” in *Sun GlassFish Enterprise Server v2.1.1 Administration Guide*.

Element Referencing

One element *references* another when an attribute of the referencing element has the same value as an attribute of the referenced element. For example, the “[application-ref](#)” on page 27 element references an application or module that is deployed to its parent “[server](#)” on page 132 element. The application-ref element’s ref attribute has the same value as the name attribute of a “[lifecycle-module](#)” on page 98, “[j2ee-application](#)” on page 81, “[ejb-module](#)” on page 57, “[web-module](#)” on page 155, “[connector-module](#)” on page 46, or “[appclient-module](#)” on page 26 element.

The referencing application-ref element might look like this:

```
<application-ref ref="MyServlet"/>
```

The referenced web-module element might look like this:

```
<web-module name="MyServlet" location="myservletdir"/>
```

Element Hierarchy

The element hierarchy for the domain.xml file is as follows. To make the hierarchy more readable, elements having “[property](#)” on page 121 as their last or only subelement are marked with a P, and the property subelements are not shown. Parent/child relationships between elements are shown, but not cardinality. For those details, see the element descriptions.

```
domain      P
.   applications
.   .   lifecycle-module      P
.   .   .   description
.   .   j2ee-application      P
.   .   .   description
.   .   .   web-service-endpoint
.   .   .   .   registry-location
.   .   .   .   transformation-rule
.   .   web-module      P
.   .   .   description
.   .   .   web-service-endpoint
.   .   .   .   registry-location
.   .   .   .   transformation-rule
.   .   ejb-module      P
.   .   .   description
.   .   .   web-service-endpoint
.   .   .   .   registry-location
.   .   .   .   transformation-rule
.   .   connector-module      P
.   .   .   description
```

```
. . . appclient-module      P
. . . . description
. . . mbean      P
. . . . description
. . extension-module      P
. . . . description
. . resources
. . . custom-resource      P
. . . . description
. . . external-jndi-resource      P
. . . . description
. . . jdbc-resource      P
. . . . description
. . . mail-resource      P
. . . . description
. . . persistence-manager-factory-resource      P
. . . . description
. . . admin-object-resource      P
. . . . description
. . . connector-resource      P
. . . . description
. . . resource-adapter-config      P
. . . jdbc-connection-pool      P
. . . . description
. . . connector-connection-pool      P
. . . . description
. . . . security-map
. . . . . principal
. . . . . user-group
. . . . . backend-principal
. configs
. . config      P
. . . http-service      P
. . . . access-log
. . . . request-processing
. . . . keep-alive
. . . . connection-pool
. . . . http-protocol
. . . . http-listener      P
. . . . . ssl
. . . . . virtual-server      P
. . . . . . http-access-log
. . . . overload-protection-service
. . . . iiop-service
. . . . . orb      P
. . . . . ssl-client-config
. . . . . . ssl
. . . . . iiop-listener      P
```

```
        . . . . . ssl
        . . . admin-service      P
        . . . . jmx-connector     P
        . . . . . ssl
        . . . das-config       P
        . . . connector-service
        . . . web-container     P
        . . . . session-config
        . . . . . session-manager
        . . . . . . manager-properties   P
        . . . . . . store-properties    P
        . . . . . session-properties   P
        . . . ejb-container      P
        . . . . ejb-timer-service   P
        . . . mdb-container      P
        . . . jms-service        P
        . . . . jms-host          P
        . . . log-service        P
        . . . . module-log-levels  P
        . . . security-service    P
        . . . . auth-realm         P
        . . . . jacc-provider      P
        . . . . audit-module       P
        . . . . message-security-config
        . . . . . provider-config    P
        . . . . . . request-policy
        . . . . . . response-policy
        . . . transaction-service  P
        . . . monitoring-service   P
        . . . . module-monitoring-levels P
        . . . diagnostic-service   P
        . . . java-config         P
        . . . . profiler           P
        . . . . . jvm-options
        . . . . . . jvm-options
        . . . availability-service P
        . . . . . web-container-availability P
        . . . . . ejb-container-availability P
        . . . . . jms-availability    P
        . . . thread-pools
        . . . . . thread-pool
        . . . alert-service        P
        . . . . . alert-subscription
        . . . . . . listener-config    P
        . . . . . . filter-config     P
        . . . group-management-service P
        . . . management-rules
        . . . . . management-rule    P
```

```
. . . . . description
. . . . . event P
. . . . . description
. . . system-property
. . . . description
servers
. . server P
. . . application-ref
. . . resource-ref
. . . system-property
. . . . description
clusters . . cluster P
. . . server-ref
. . . . health-checker
. . . resource-ref
. . . application-ref
. . . system-property
. . . . description
node-agents
. . node-agent P
. . . jmx-connector P
. . . . ssl
. . . auth-realm P
. . . log-service P
. . . . module-log-levels P
lb-configs
. . lb-config P
. . . cluster-ref
. . . . health-checker
. . . server-ref
. . . . health-checker
load-balancers
. . load-balancer P
system-property
. . description
```

Alphabetical List of Elements

“A” on page 22 “B” on page 35 “C” on page 36 “D” on page 50 “E” on page 54 “F” on page 66
“G” on page 67 “H” on page 68 “I” on page 79 “J” on page 81 “K” on page 96 “L” on page 97
“M” on page 104 “N” on page 115 “O” on page 117 “P” on page 119 “R” on page 125 “S” on
page 130 “T” on page 141 “U” on page 146 “V” on page 146 “W” on page 151

A

access-log

Defines access log settings for each “[http-access-log](#)” on page 69 subelement of each “[virtual-server](#)” on page 146.

Superelements

[“http-service” on page 76](#)

Subelements

none

Attributes

The following table describes attributes for the `access-log` element.

TABLE 1-1 `access-log` Attributes

Attribute	Default	Description
<code>format</code>	<code>%client.name% %auth-user-name% %datetime% %request% %status% %response.length%</code>	(optional) Specifies the format of the access log. For a complete list of token values you can use in the format, see the online help for the Access Log tab of the HTTP Service page in the Admin Console.
<code>rotation-policy</code>	<code>time</code>	(optional) Specifies the condition that triggers log rotation. The only legal value is <code>time</code> , which rotates log files at the <code>rotation-interval-in-minutes</code> interval.
<code>rotation-interval-in-minutes</code>	15 (developer profile) 1440 (cluster and enterprise profiles)	(optional) Specifies the time interval between log rotations if <code>rotation-policy</code> is set to <code>time</code> .
<code>rotation-suffix</code>	<code>yyyy-MM-dd</code> (developer profile) <code>yyyyMMdd-HH'h'mm'm's's'</code> (cluster and enterprise profiles)	(optional) Specifies the format of the timestamp appended to the access log name when log rotation occurs. For supported formats, see http://java.sun.com/javase/6/docs/api/java/text/SimpleDateFormat.html . The following value is supported for backward compatibility. It results in the same format as the default. <code>%YYYY;%MM;%DD; -%hh;h%mm;m%ss;s</code>
<code>rotation-enabled</code>	<code>true</code>	(optional) If <code>true</code> , enables log rotation.

action

Specifies the action of a management rule. The action is implemented as an MBean.

Superelements

[“management-rule” on page 106](#)

Subelements

none

Attributes

The following table describes attributes for the `action` element.

TABLE 1–2 `action` Attributes

Attribute	Default	Description
<code>action-mbean-name</code>	none	Specifies the name of the “ mbean ” on page 109 that performs the action of a management rule. This MBean must implement <code>javax.management.NotificationListener</code> .

admin-object-resource

Defines an administered object for an inbound resource adapter.

Superelements

[“resources” on page 128](#)

Subelements

The following table describes subelements for the `admin-object-resource` element.

TABLE 1–3 `admin-object-resource` Subelements

Element	Required	Description
“description” on page 51	zero or one	Contains a text description of this element.
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

The following table describes attributes for the `admin-object-resource` element.

TABLE 1-4 admin-object-resource Attributes

Attribute	Default	Description
jndi-name	none	Specifies the JNDI name for the resource.
res-type	none	Specifies the fully qualified type of the resource.
res-adapter	none	Specifies the name of the inbound resource adapter, as specified in the name attribute of a “connector-module” on page 46 element.
object-type	user	(optional) Defines the type of the resource. Allowed values are: <ul style="list-style-type: none"> ■ system-all - A system resource for all server instances and the domain application server. ■ system-admin - A system resource only for the domain application server. ■ system-instance - A system resource for all server instances only. ■ user - A user resource.
enabled	true	(optional) Determines whether this resource is enabled at runtime.

Properties

Properties of the `admin-object-resource` element are the names of setter methods of the `adminobject-class` specified in the `adminobject` element of the `ra.xml` file. Some of the property names can be specified in the `adminobject` element itself. For example, in `jmsra`, the resource adapter used to communicate with the Sun Java System Message Queue software, `jmsra`, `Name` and `Description` are valid properties.

For a complete list of the available properties (called *administered object attributes* in the Message Queue software), see the [Sun GlassFish Message Queue 4.4 Administration Guide](#).

admin-service

Determines whether the server instance is a regular instance, a domain administration server, or a combination.

Superelements

[“config” on page 40](#)

Subelements

The following table describes subelements for the `admin-service` element.

TABLE 1–5 admin-service Subelements

Element	Required	Description
“jmx-connector” on page 94	zero or more	Configures a JSR 160/255 compliant remote JMX connector.
“das-config” on page 50	only one (developer profile) zero or one (cluster and enterprise profiles)	Defines a domain administration server configuration.
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

The following table describes attributes for the `admin-service` element.

TABLE 1–6 admin-service Attributes

Attribute	Default	Description
type	das-and-server (developer profile) server (cluster and enterprise profiles)	Specifies whether the server instance is a regular instance (server), a domain administration server (das), or a combination (das-and-server). modifying this value is not recommended.
system-jmx-connector-name	none	Specifies the name of the internal “jmx-connector” on page 94.

alert-service

Configures the alert service, which allows you to register for and receive system status alerts.

Superelements

“config” on page 40

Subelements

The following table describes subelements for the `alert-service` element.

TABLE 1–7 alert-service Subelements

Element	Required	Description
“alert-subscription” on page 26	zero or more	Configures a subscription to system status alerts.

TABLE 1-7 alert-service Subelements *(Continued)*

Element	Required	Description
“property” on page 121	zero or more	Specifies a property or a variable.

alert-subscription

Configures a subscription to system status alerts.

Superelements

[“alert-service” on page 25](#)

Subelements

The following table describes subelements for the `alert-subscription` element.

TABLE 1-8 alert-subscription Subelements

Element	Required	Description
“listener-config” on page 99	only one	Configures the listener class that listens for alerts from notification emitters.
“filter-config” on page 66	zero or one	Configures the filter class that filters alerts from notification emitters.

Attributes

The following table describes attributes for the `alert-subscription` element.

TABLE 1-9 alert-subscription Attributes

Attribute	Default	Description
name	none	Specifies the name of this alert subscription.

appclient-module

Specifies a deployed application client container (ACC) module.

Superelements

[“applications” on page 28](#)

Subelements

The following table describes subelements for the `appclient-module` element.

TABLE 1–10 appclient-module Subelements

Element	Required	Description
“description” on page 51	zero or one	Contains a text description of this element.
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

The following table describes attributes for the `appclient-module` element.

TABLE 1–11 appclient-module Attributes

Attribute	Default	Description
name	none	The name of the ACC module.
location	none	The location of the ACC module in the Enterprise Server file system.
directory-deployed	false	(optional) Specifies whether the application has been deployed as a directory.
java-web-start-enabled	true	(optional) Specifies whether Java Web Start access is permitted for this application client.

application-ref

References an application or module deployed to the server instance or cluster.

Note – Some topics in the documentation pertain to features that are available only in domains that are configured to support clusters. Examples of domains that support clusters are domains that are created with the cluster profile or the enterprise profile. For information about profiles, see “[Usage Profiles](#)” in *Sun GlassFish Enterprise Server v2.1.1 Administration Guide*.

Superelements

“cluster” on page 36, “server” on page 132

Subelements

none

Attributes

The following table describes attributes for the `application-ref` element.

TABLE 1–12 application-ref Attributes

Attribute	Default	Description
enabled	true	(optional) Determines whether the application or module is enabled.
virtual-servers	all virtual servers	(optional) In a comma-separated list, references id attributes of the “virtual-server” on page 146 elements to which the “web-module” on page 155 or the web modules within this “j2ee-application” on page 81 are deployed.
lb-enabled	false	(optional) If true, all load-balancers that reference this application consider it available to them.
disable-timeout-in-minutes	30	(optional) Specifies the time it takes this application to reach a quiescent state after having been disabled.
ref	none	References the name attribute of a “lifecycle-module” on page 98, “j2ee-application” on page 81, “ejb-module” on page 57, “web-module” on page 155, “connector-module” on page 46, “appclient-module” on page 26, or “extension-module” on page 64 element.

applications

Contains deployed Java EE applications, Java EE modules, and Lifecycle modules.

Superelements

[“domain” on page 53](#)

Subelements

The following table describes subelements for the applications element.

TABLE 1–13 applications Subelements

Element	Required	Description
“lifecycle-module” on page 98	zero or more	Specifies a deployed lifecycle module.
“j2ee-application” on page 81	zero or more	Specifies a deployed Java EE application.
“ejb-module” on page 57	zero or more	Specifies a deployed EJB module.
“web-module” on page 155	zero or more	Specifies a deployed web module.
“connector-module” on page 46	zero or more	Specifies a deployed connector module.
“appclient-module” on page 26	zero or more	Specifies a deployed application client container (ACC) module.
“mbean” on page 109	zero or more	Specifies an MBean.
“extension-module” on page 64	zero or more	Specifies an extension module.

Note – Subelements of an `applications` element can occur in any order.

audit-module

Specifies an optional plug-in module that implements audit capabilities.

Superelements

[“security-service” on page 131](#)

Subelements

The following table describes subelements for the `audit-module` element.

TABLE 1–14 audit-module Subelements

Element	Required	Description
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

The following table describes attributes for the `audit-module` element.

TABLE 1–15 audit-module Attributes

Attribute	Default	Description
<code>name</code>	<code>default</code>	Specifies the name of this audit module.
<code>classname</code>	<code>com.sun.enterprise.security.Audit</code>	Specifies the Java class that implements this audit module.

auth-realm

Defines a realm for authentication.

Authentication realms require provider-specific properties, which vary depending on what a particular implementation needs.

For more information about how to define realms, see the [Sun GlassFish Enterprise Server v2.1.1 Administration Guide](#).

Here is an example of the default `file` realm:

```
<auth-realm name="file"
    classname="com.sun.enterprise.security.auth.realm.file.FileRealm">
    <property name="file" value="domain-dir/config/keyfile"/>
    <property name="jaas-context" value="fileRealm"/>
</auth-realm>
```

Which properties an auth-realm element uses depends on the value of the auth-realm element's name attribute. The file realm uses file and jaas-context properties. Other realms use different properties.

Superelements

[“node-agent” on page 115](#), [“security-service” on page 131](#)

Subelements

The following table describes subelements for the auth-realm element.

TABLE 1–16 auth-realm Subelements

Element	Required	Description
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

The following table describes attributes for the auth-realm element.

TABLE 1–17 auth-realm Attributes

Attribute	Default	Description
name	none	Specifies the name of this realm.
classname	none	Specifies the Java class that implements this realm.

Properties

The standard realms provided with Enterprise Server have required and optional properties. A custom realm might have different properties.

The following table describes properties for the auth-realm element.

TABLE 1–18 auth-realm Properties

Property	Realms	Description
jaas-context	file, ldap, jdbc, solaris	Specifies the JAAS (Java Authentication and Authorization Service) context.
file	file	Specifies the file that stores user names, passwords, and group names. The default is <i>domain-dir/config/keyfile</i> .
assign-groups	certificate, file, jdbc, ldap, solaris	(optional) If this property is set, its value is taken to be a comma-separated list of group names. All clients who present valid certificates are assigned membership to these groups for the purposes of authorization decisions in the web and EJB containers.
directory	ldap	Specifies the LDAP URL to your server.
base-dn	ldap	Specifies the LDAP base DN for the location of user data. This base DN can be at any level above the user data, since a tree scope search is performed. The smaller the search tree, the better the performance.
search-filter	ldap	(optional) Specifies the search filter to use to find the user. The default is <code>uid=%s</code> (%s expands to the subject name).
group-base-dn	ldap	(optional) Specifies the base DN for the location of groups data. By default, it is same as the <code>base-dn</code> , but it can be tuned, if necessary.
group-search-filter	ldap	(optional) Specifies the search filter to find group memberships for the user. The default is <code>uniquemember=%d</code> (%d expands to the user element DN).
group-target	ldap	(optional) Specifies the LDAP attribute name that contains group name entries. The default is <code>CN</code> .
search-bind-dn	ldap	(optional) Specifies an optional DN used to authenticate to the directory for performing the <code>search-filter</code> lookup. Only required for directories that do not allow anonymous search.
search-bind-password	ldap	(optional) Specifies the LDAP password for the DN given in <code>search-bind-dn</code> .
datasource-jndi	jdbc	Specifies the jndi-name of the “ jdbc-resource ” on page 89 for the database.
user-table	jdbc	Specifies the name of the user table in the database.
user-name-column	jdbc	Specifies the name of the user name column in the database's user table.
password-column	jdbc	Specifies the name of the password column in the database's user table.
group-table	jdbc	Specifies the name of the group table in the database.
group-name-column	jdbc	Specifies the name of the group name column in the database's group table.
db-user	jdbc	(optional) Allows you to specify the database user name in the realm instead of the “ jdbc-connection-pool ” on page 85. This prevents other applications from looking up the database, getting a connection, and browsing the user table. By default, the <code>jdbc-connection-pool</code> configuration is used.

TABLE 1–18 auth-realm Properties (Continued)

Property	Realms	Description
db-password	jdbc	(optional) Allows you to specify the database password in the realm instead of the “ jdbc-connection-pool ” on page 85. This prevents other applications from looking up the database, getting a connection, and browsing the user table. By default, the jdbc-connection-pool configuration is used.
digest-algorithm	jdbc	(optional) Specifies the digest algorithm. The default is MD5. You can use any algorithm supported in the JDK, or none.
encoding	jdbc	(optional) Specifies the encoding. Allowed values are Hex and Base64. If digest-algorithm is specified, the default is Hex. If digest-algorithm is not specified, by default no encoding is specified.
charset	jdbc	(optional) Specifies the charset for the digest algorithm.

availability-service

Configures the availability service. Enables high-availability features, such as session state and stateful session bean state persistence. If the Sun Java System high-availability database (HADB) is installed and you have selected the enterprise profile, session state is persisted to the HADB.

Note – Some topics in the documentation pertain to features that are available only in domains that are configured to support clusters. Examples of domains that support clusters are domains that are created with the cluster profile or the enterprise profile. For information about profiles, see “[Usage Profiles](#)” in *Sun GlassFish Enterprise Server v2.1.1 Administration Guide*.

Availability can be enabled or disabled at the following levels:

1. The server instance (attribute of `availability-service`). Default is `true` (enabled).
2. The EJB or web container (attribute of “[ejb-container-availability](#)” on page 56 or “[web-container-availability](#)” on page 152). Default is `true` (enabled).
3. The application (attribute of “[j2ee-application](#)” on page 81). Default is `false` (disabled).
4. The stand-alone EJB or web module (attribute of “[ejb-module](#)” on page 57 or “[web-module](#)” on page 155). Default is `false` (disabled).
5. The stateful session bean. Default is `false` (disabled). See the *Sun GlassFish Enterprise Server v2.1.1 Developer’s Guide*.

For availability to be enabled at a given level, it must be enabled at all higher levels, as well. For example, to enable availability at the application level, you must also enable it at the server instance and container levels.

If the HADB is installed and the enterprise profile is selected, availability can also be enabled in the Java Message Service (attribute of “[jms-availability](#)” on page 90). The default is `false` (disabled). JMS availability is disabled if server instance availability is disabled. JMS availability neither affects nor is affected by any other availability levels.

Superelements

[“config” on page 40](#)

Subelements

The following table describes subelements for the `availability-service` element.

TABLE 1-19 `availability-service` Subelements

Element	Required	Description
“ web-container-availability ” on page 152	zero or one	Enables availability in the web container.
“ ejb-container-availability ” on page 56	zero or one	Enables availability in the EJB container.
“ jms-availability ” on page 90	zero or one	Enables availability in the Java Message Service.
“ property ” on page 121	zero or more	Specifies a property or a variable.

Attributes

The following table describes attributes for the `availability-service` element.

TABLE 1-20 `availability-service` Attributes

Attribute	Default	Description
<code>availability-enabled</code>	<code>true</code>	(optional) If set to <code>true</code> , high-availability features apply to all applications deployed to the server instance that do not have availability disabled. All instances in a cluster should have the same availability value to ensure consistent behavior.
<code>ha-agent-hosts</code>	<code>none</code>	Specifies a comma-separated list of server host names or IP addresses where management agents for the high availability store are running. Applicable if HADB is installed and you have selected the enterprise profile.
<code>ha-agent-port</code>	<code>none</code>	Specifies the port number where management agents for the high availability store can be contacted. Applicable if HADB is installed and you have selected the enterprise profile.
<code>ha-agent-password</code>	<code>asadmin password</code>	Specifies the password for access to management agents for the high availability store. Applicable if HADB is installed and you have selected the enterprise profile.
<code>ha-store-name</code>	cluster name	(optional) Specifies the HADB database name. Applicable if HADB is installed and you have selected the enterprise profile.

TABLE 1–20 availability-service Attributes *(Continued)*

Attribute	Default	Description
auto-manage-ha-store	true	(optional) If true, the life cycle of the highly available store is matched with the life cycle of the highly available cluster. The store is started or stopped with the cluster. It is removed when the cluster is deleted. If false, the store life cycle must be manually managed by the administrator. Applicable if HADB is installed and you have selected the enterprise profile.
store-pool-name	jdbc/hastore	(optional) Specifies the jndi-name of the “jdbc-resource” on page 89 used for connections to the HADB for session persistence. Applicable if HADB is installed and you have selected the enterprise profile. For more information about setting up a connection pool and JDBC resource for the HADB, see the description of the configure-ha-cluster command in the <i>Sun GlassFish Enterprise Server v2.1.1 Reference Manual</i> .
ha-store-healthcheck-enabled	false	(optional) If true, periodic checking is done to detect if the HADB has become available again after a failure. If the health check succeeds, persistence to the HADB is resumed. Applicable if HADB is installed and you have selected the enterprise profile.
ha-store-healthcheck-interval-in-seconds	5	(optional) Specifies the interval at which the HADB's health is checked. The checking begins only after a failure is detected. Applicable if HADB is installed and you have selected the enterprise profile.

Properties

The following table describes properties for the availability-service element. For more information about replicated session persistence, see “web-container-availability” on page 152 and “ejb-container-availability” on page 56.

TABLE 1–21 availability-service Properties

Attribute	Default	Description
replication_measurement_enabled	false	If true, logs measurements of replication times. One of these messages appears in the sending instance's log: <code>messageSendSucceeded: id = session-id fastAckTime = 8 to partner: instance-name</code> <code>messageSendFailed: id = session-id fastAckTime = 8 to partner: instance-name</code> This message appears in the receiving instance's log: <code>messageReceiptSucceeded: bulkId = 1 receiptTime = 12 from partner: instance-name</code>

TABLE 1-21 availability-service Properties *(Continued)*

Attribute	Default	Description
replication_measurement_interval	1	Specifies the frequency of measurement of replication. It must be a positive integer: 1 means every replication, 2 means once every 2 replications, 3 means once every 3 replications, and so on. Applicable only if replication_measurement_enabled is set to true.
rolling-upgrade-backup-directory	<i>instance-dir/rollingupgrade</i>	Specifies where the <code>asadmin backup-session-store</code> command backs up active and replica sessions.

B**backend-principal**

Specifies the user name and password required by the Enterprise Information System (EIS).

Superelements

[“security-map” on page 130](#)

Subelements

none

Attributes

The following table describes attributes for the `backend-principal` element.

TABLE 1-22 `backend-principal` Attributes

Attribute	Default	Description
user-name	none	Specifies the user name required by the EIS.
password	none	(optional) Specifies the password required by the EIS, if any.

cluster

Defines a cluster.

Note – Some topics in the documentation pertain to features that are available only in domains that are configured to support clusters. Examples of domains that support clusters are domains that are created with the cluster profile or the enterprise profile. For information about profiles, see “[Usage Profiles](#)” in *Sun GlassFish Enterprise Server v2.1.1 Administration Guide*.

Superelements

[“clusters” on page 39](#)

Subelements

The following table describes subelements for the `cluster` element.

TABLE 1–23 cluster Subelements

Element	Required	Description
“server-ref” on page 133	zero or more	References a server instance that belongs to the cluster.
“resource-ref” on page 127	zero or more	References a resource deployed to the cluster.
“application-ref” on page 27	zero or more	References an application or module deployed to the cluster.
“system-property” on page 139	zero or more	Specifies a system property.
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

The following table describes attributes for the `cluster` element.

TABLE 1–24 cluster Attributes

Attribute	Default	Description
<code>name</code>	none	Specifies the name of the cluster.

TABLE 1–24 cluster Attributes (Continued)

Attribute	Default	Description
config-ref	default “config” on page 40 element’s name attribute value, server-config	References the configuration used by the cluster.
heartbeat-port	none; value automatically generated	Specifies the communication port the Group Management Service uses to listen for group events. Must be a valid port number.
heartbeat-address	none; value automatically generated	Specifies the address the Group Management Service uses to listen for group events. Must be a multicast address.
heartbeat-enabled	false (developer profile) true (cluster and enterprise profiles)	(optional) If true, the Group Management Service is started as a lifecycle module in each server instance in the cluster and in the Domain Administration Server. The Domain Administration Server participates in each cluster that has this attribute set to true.

Properties

The following table describes properties for the `cluster` element.

TABLE 1–25 cluster Properties

Property	Default	Description
gms-bind-interface-address	none	<p>Specifies which address the group management service uses on a multi-home machine. If a machine has only one network interface, there is no need to set this property.</p> <p>If this property is not set or is set to an invalid value on a multi-home machine, Enterprise Server uses all available addresses. The primary address is nondeterministic, because the ordering of addresses is specific to the operating system, not the Java network API used to access the network interfaces.</p> <p>You can create “system-property” on page 139 elements to set this value differently for each server instance in the cluster. For example:</p> <pre><domain> ... <clusters> <cluster name="cluster1" ... > ... <property name="gms-bind-interface-address" value="\${GMS_CLUSTER1_BIND_IF_ADDR}"/> </cluster> ... </clusters> ... <servers> <server name="server1" ... > ... <system-property name="GMS_CLUSTER1_BIND_IF_ADDR" value="123.456.78.910"/> </server> ... </servers> ... </domain></pre>

cluster-ref

References a cluster.

Note – Some topics in the documentation pertain to features that are available only in domains that are configured to support clusters. Examples of domains that support clusters are domains that are created with the cluster profile or the enterprise profile. For information about profiles, see “[Usage Profiles](#)” in *Sun GlassFish Enterprise Server v2.1.1 Administration Guide*.

Superelements

[“lb-config” on page 97](#)

Subelements

The following table describes subelements for the `cluster-ref` element.

TABLE 1-26 `cluster-ref` Subelements

Element	Required	Description
“health-checker” on page 68	zero or one	Defines a health checker for the referenced cluster.

Attributes

The following table describes attributes for the `cluster-ref` element.

TABLE 1-27 `cluster-ref` Attributes

Attribute	Default	Description
<code>ref</code>	none	References the <code>name</code> attribute of a “cluster” on page 36 element.
<code>lb-policy</code>	<code>round-robin</code>	(optional) Specifies the load balancing policy. Allowed values are: <ul style="list-style-type: none"> ■ <code>round-robin</code> — The load balancer cycles through the cluster's server instances in a specified order. ■ <code>weighted-round-robin</code> — The load balancer cycles through the server instances in a specified order, but routes more requests to instances with greater processing capacity. Processing capacity is represented by values of the <code>lb-weight</code> attribute of each “server” on page 132 element referenced by the cluster. ■ <code>user-defined</code> — The load balancing policy is defined in a custom module.
<code>lb-policy-module</code>	none	(optional) Specifies the absolute path to the shared library that implements the user-defined policy. The shared library must exist and be readable on the machine where the load balancer is running. Required only if <code>lb-policy</code> is set to <code>user-defined</code> .

clusters

Contains clusters.

Superelements

[“domain” on page 53](#)

Subelements

The following table describes subelements for the `clusters` element.

TABLE 1–28 `clusters` Subelements

Element	Required	Description
“cluster” on page 36	zero or more	Defines a cluster.

config

Defines a configuration, which is a collection of settings that controls how a server instance functions.

Superelements

[“configs” on page 41](#)

Subelements

The following table describes subelements for the `config` element.

TABLE 1–29 `config` Subelements

Element	Required	Description
“http-service” on page 76	only one	Configures the HTTP service.
“overload-protection-service” on page 118	only one	Configures the overload protection service for HTTP requests.
“iiop-service” on page 80	only one	Configures the IIOP service.
“admin-service” on page 24	only one	Determines whether the server to which the configuration applies is an administration server.
“connector-service” on page 48	zero or one	Configures the connector service.
“web-container” on page 151	only one	Configures the web container.
“ejb-container” on page 54	only one	Configures the Enterprise JavaBeans™ (EJB™) container.
“mdb-container” on page 110	only one	Configures the message-driven bean (MDB) container.
“jms-service” on page 92	zero or one	Configures the Java Message Service (JMS) provider.
“log-service” on page 102	only one	Configures the system logging service.
“security-service” on page 131	only one	Configures the Java EE security service.

TABLE 1-29 config Subelements (*Continued*)

Element	Required	Description
“transaction-service” on page 142	only one	Configures the transaction service.
“monitoring-service” on page 115	only one	Configures the monitoring service.
“diagnostic-service” on page 52	zero or one	Configures the diagnostic service.
“java-config” on page 83	only one	Configures the Java Virtual Machine (JVM™).
“availability-service” on page 32	zero or one	Configures the availability service.
“thread-pools” on page 142	only one	Configures thread pools.
“alert-service” on page 25	zero or one	Configures the alert service.
“group-management-service” on page 67	zero or one	Configures the group management service.
“management-rules” on page 107	zero or one	Configures self-management rules.
“system-property” on page 139	zero or more	Specifies a system property.
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

The following table describes attributes for the config element.

TABLE 1-30 config Attributes

Attribute	Default	Description
name	server-config (for default instance)	Specifies the name of the configuration.
dynamic-reconfiguration-enabled	true	(optional) If true, any changes to the system (for example, applications deployed, resources created) are automatically applied to the affected servers without a restart being required. If false, such changes are only picked up by the affected servers when each server restarts.

configs

Contains configurations.

Superelements

“domain” on page 53

Subelements

The following table describes subelements for the `configs` element.

TABLE 1-31 `configs` Subelements

Element	Required	Description
“config” on page 40	only one (developer profile) one or more (cluster and enterprise profiles)	Defines a configuration.

connection-pool

Defines a pool of client HTTP connections used by the “[http-listener](#)” on page 71 subelements of the parent “[http-service](#)” on page 76 element.

Superelements

[“http-service” on page 76](#)

Subelements

none

Attributes

The following table describes attributes for the `connection-pool` element.

TABLE 1-32 `connection-pool` Attributes

Attribute	Default	Description
queue-size-in-bytes	-1	(optional) Specifies the maximum number of messages that can be queued until threads are available to process them for “ http-listener ” on page 71 elements. A value of -1 specifies no limit.
max-pending-count	4096	(optional) Specifies the maximum number of pending connections on an “ http-listener ” on page 71.
receive-buffer-size-in-bytes	4096	(optional) Specifies the size of the receive buffer for all “ http-listener ” on page 71 elements. A value of -1 specifies no limit.
send-buffer-size-in-bytes	8192	(optional) Specifies the size of the send buffer for all “ http-listener ” on page 71 elements.

connector-connection-pool

Defines a connector connection pool.

Superelements

[“resources” on page 128](#)

Subelements

The following table describes subelements for the connector-connection-pool element.

TABLE 1-33 connector-connection-pool Subelements

Element	Required	Description
“description” on page 51	zero or one	Contains a text description of this element.
“security-map” on page 130	zero or more	Maps the principal received during servlet or EJB authentication to the credentials accepted by the EIS.
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

The following table describes attributes for the connector-connection-pool element. Changing the following attributes requires a server restart: resource-adapter-name, connection-definition-name, transaction-support, associate-with-thread, lazy-connection-association, and lazy-connection-enlistment.

TABLE 1-34 connector-connection-pool Attributes

Attribute	Default	Description
name	none	Specifies the name of the connection pool. A “ connector-resource ” on page 47 element’s pool-name attribute refers to this name.
resource-adapter-name	none	Specifies the name attribute of the deployed “ connector-module ” on page 46. If no name is specified during deployment, the name of the .rar file is used. If the resource adapter is embedded in an application, then it is <i>app_name#rar_name</i> .
connection-definition-name	none	Specifies a unique name, identifying a resource adapter’s connection-definition element in the ra.xml file. This is usually the connectionfactory-interface of the connection-definition element.
steady-pool-size	8	(optional) Specifies the initial and minimum number of connections maintained in the pool.
max-pool-size	32	(optional) Specifies the maximum number of connections that can be created to satisfy client requests.
max-wait-time-in-millis	60000	(optional) Specifies the amount of time, in milliseconds, that the caller is willing to wait for a connection. If 0, the caller is blocked indefinitely until a resource is available or an error occurs.

TABLE 1-34 connector-connection-pool Attributes (Continued)

Attribute	Default	Description
pool-resize-quantity	2	(optional) Specifies the number of idle connections to be destroyed if the existing number of connections is above the steady-pool-size (subject to the max-pool-size limit). This is enforced periodically at the idle-timeout-in-seconds interval. An idle connection is one that has not been used for a period of idle-timeout-in-seconds. When the pool size reaches steady-pool-size, connection removal stops.
idle-timeout-in-seconds	300	(optional) Specifies the maximum time that a connection can remain idle in the pool. After this amount of time, the pool can close this connection.
fail-all-connections	false	(optional) If true, closes all connections in the pool if a single validation check fails.
transaction-support	none	(optional) Specifies the transaction support for this connection pool. Overrides the transaction support defined in the resource adapter in a downward compatible way: supports a transaction level lower than or equal to the resource adapter's, but not higher. Allowed values in descending order are: <ul style="list-style-type: none">■ XATransaction - Supports distributed transactions.■ LocalTransaction - Supports local transactions only.■ NoTransaction - No transaction support.
is-connection-validation-required	false	(optional) Specifies whether connections have to be validated before being given to the application. If a resource's validation fails, it is destroyed, and a new resource is created and returned.
connection-leak-timeout-in-seconds	0	Detects potential connection leaks by the application. A connection that is not returned back to the pool by the application within the specified period is assumed to be potentially leaking, and a stack trace of the caller is logged. A zero value disables leak detection. A nonzero value enables leak tracing.
connection-leak-reclaim	false	If true, the pool will reclaim a connection after connection-leak-timeout-in-seconds occurs.
connection-creation-retry-attempts	0	Specifies the number of attempts to create a new connection.
connection-creation-retry-interval-in-seconds	10	Specifies the time interval between attempts to create a connection when connection-creation-retry-attempts is greater than 0.
validate-atmost-once-period-in-seconds	60	Specifies the time interval within which a connection is validated at most once. Minimizes the number of validation calls.
lazy-connection-enlistment	false	If true, a connection is not enlisted in a transaction until it is used. If false, any connection object available to a transaction is enlisted in the transaction.
lazy-connection-association	false	If true, a physical connection is not associated with a logical connection until it is used. If false, a physical connection is associated with a logical connection even before it is used.

TABLE 1-34 connector-connection-pool Attributes *(Continued)*

Attribute	Default	Description
associate-with-thread	false	If true, allows a connection to be saved as a <code>ThreadLocal</code> in the calling thread. This connection gets reclaimed only when the calling thread dies or when the calling thread is not in use and the pool has run out of connections.
match-connections	true	If true, enables connection matching. You can set to false if connections are homogeneous.
max-connection-usage-count	0	Specifies the number of times a connection is reused by the pool, after which it is closed. A zero value disables this feature.

Properties

Most properties of the `connector-connection-pool` element are the names of setter methods of the `managedconnectionfactory-class` element in the `ra.xml` file. Properties of the `connector-connection-pool` element override the `ManagedConnectionFactory` JavaBean configuration settings.

All but the last four properties in the following table are `connector-connection-pool` properties of `jms-ra`, the resource adapter used to communicate with the Sun GlassFish Message Queue software. For a complete list of the available properties (called *administered object attributes* in the Message Queue software), see the [Sun GlassFish Message Queue 4.4 Administration Guide](#).

Changes to `connector-connection-pool` properties require a server restart.

TABLE 1-35 connector-connection-pool Properties

Property	Default	Description
AddressList	none	Specifies a list of host/port combinations of the Message Queue software. For JMS resources of the Type <code>javax.jms.TopicConnectionFactory</code> or <code>javax.jms.QueueConnectionFactory</code> .
ClientId	none	<p>Specifies the JMS Client Identifier to be associated with a Connection created using the <code>createTopicConnection</code> method of the <code>TopicConnectionFactory</code> class. For JMS resources of the Type <code>javax.jms.TopicConnectionFactory</code>.</p> <p>Durable subscription names are unique and only valid within the scope of a client identifier. To create or reactivate a durable subscriber, the connection must have a valid client identifier. The JMS specification ensures that client identifiers are unique and that a given client identifier is allowed to be used by only one active connection at a time.</p>
UserName	guest	Specifies the user name for connecting to the Message Queue software. For JMS resources of the Type <code>javax.jms.TopicConnectionFactory</code> or <code>javax.jms.QueueConnectionFactory</code> .
Password	guest	Specifies the password for connecting to the Message Queue software. For JMS resources of the Type <code>javax.jms.TopicConnectionFactory</code> or <code>javax.jms.QueueConnectionFactory</code> .

TABLE 1-35 connector-connection-pool Properties *(Continued)*

Property	Default	Description
ReconnectAttempts	6	Specifies the number of attempts to connect (or reconnect) for each address in the <code>imqAddressList</code> before the client runtime moves on to try the next address in the list. A value of -1 indicates that the number of reconnect attempts is unlimited (the client runtime attempts to connect to the first address until it succeeds).
ReconnectInterval	30000	Specifies the interval between reconnect attempts in milliseconds. This applies to attempts on each address in the <code>imqAddressList</code> and on successive addresses in the list. If too short, this time interval does not give a broker time to recover. If too long, the reconnect might represent an unacceptable delay.
ReconnectEnabled	false	If true, specifies that the client runtime attempts to reconnect to a message server (or the list of addresses in <code>imqAddressList</code>) when a connection is lost.
AddressListBehavior	priority	Specifies whether connection attempts are in the order of addresses in the <code>imqAddressList</code> attribute (<code>priority</code>) or in a random order (<code>random</code>). If many clients are attempting a connection using the same connection factory, use a random order to prevent them from all being connected to the same address.
AddressListIterations	-1	Specifies the number of times the client runtime iterates through the <code>imqAddressList</code> in an effort to establish (or reestablish) a connection. A value of -1 indicates that the number of attempts is unlimited.
LazyConnectionEnlistment	false	Deprecated. Use the equivalent attribute.
LazyConnectionAssociation	false	Deprecated. Use the equivalent attribute.
AssociateWithThread	false	Deprecated. Use the equivalent attribute.
MatchConnections	true	Deprecated. Use the equivalent attribute.

Note – All JMS administered object resource properties that worked with version 7 of the Enterprise Server are supported for backward compatibility.

connector-module

Specifies a deployed connector module.

Superelements

[“applications” on page 28](#)

Subelements

The following table describes subelements for the `connector-module` element.

TABLE 1-36 connector-module Subelements

Element	Required	Description
“description” on page 51	zero or one	Contains a text description of this element.
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

The following table describes attributes for the connector-module element.

TABLE 1-37 connector-module Attributes

Attribute	Default	Description
name	none	The name of the connector module.
location	none	The location of the connector module in the Enterprise Server file system.
object-type	user	(optional) Defines the type of the resource. Allowed values are: <ul style="list-style-type: none"> ■ system-all - A system resource for all server instances and the domain application server. ■ system-admin - A system resource only for the domain application server. ■ system-instance - A system resource for all server instances only. ■ user - A user resource.
enabled	true	(optional) Determines whether the connector module is enabled.
directory-deployed	false	(optional) Specifies whether the application has been deployed as a directory.

connector-resource

Defines the connection factory object of a specific connection definition in a connector (resource adapter).

Superelements

“resources” on page 128

Subelements

The following table describes subelements for the connector-resource element.

TABLE 1–38 connector-resource Subelements

Element	Required	Description
“description” on page 51	zero or one	Contains a text description of this element.
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

The following table describes attributes for the connector-resource element.

TABLE 1–39 connector-resource Attributes

Attribute	Default	Description
jndi-name	none	Specifies the JNDI name for the resource.
pool-name	none	Specifies the name of the associated connector connection pool, defined in a “connector-connection-pool” on page 42 element.
object-type	user	(optional) Defines the type of the resource. Allowed values are: <ul style="list-style-type: none"> ■ system-all - A system resource for all server instances and the domain application server. ■ system-admin - A system resource only for the domain application server. ■ system-instance - A system resource for all server instances only. ■ user - A user resource.
enabled	true	(optional) Determines whether this resource is enabled at runtime.

connector-service

Configures the connector service.

Superelements

“config” on page 40

Subelements

none

Attributes

The following table describes attributes for the connector-service element.

TABLE 1–40 connector-service Attributes

Attribute	Default	Description
shutdown-timeout-in-seconds	30	(optional) Specifies the maximum time allowed during application server shutdown for the <code>ResourceAdapter.stop()</code> method of a connector module's instance to complete. Resource adapters that take longer to shut down are ignored, and Enterprise Server shutdown continues.

custom-resource

Defines a custom resource, which specifies a custom server-wide resource object factory. Such object factories implement the `javax.naming.spi.ObjectFactory` interface.

Superelements

[“resources” on page 128](#)

Subelements

The following table describes subelements for the `custom-resource` element.

TABLE 1–41 custom-resource Subelements

Element	Required	Description
“description” on page 51	zero or one	Contains a text description of this element.
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

The following table describes attributes for the `custom-resource` element.

TABLE 1–42 custom-resource Attributes

Attribute	Default	Description
<code>jndi-name</code>	none	Specifies the JNDI name for the resource.
<code>res-type</code>	none	Specifies the fully qualified type of the resource.
<code>factory-class</code>	none	Specifies the fully qualified name of the user-written factory class, which implements <code>javax.naming.spi.ObjectFactory</code> .

TABLE 1–42 custom-resource Attributes *(Continued)*

Attribute	Default	Description
object-type	user	(optional) Defines the type of the resource. Allowed values are: <ul style="list-style-type: none"> ■ system-all - A system resource for all server instances and the domain application server. ■ system-admin - A system resource only for the domain application server. ■ system-instance - A system resource for all server instances only. ■ user - A user resource.
enabled	true	(optional) Determines whether this resource is enabled at runtime.

D

das-config

Defines a domain administration server configuration. The domain administration server runs the Administration Console.

Superelements

[“admin-service” on page 24](#)

Subelements

The following table describes subelements for the das-config element.

TABLE 1–43 das-config Subelements

Element	Required	Description
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

The following table describes attributes for the das-config element. For more information about deployment topics such as dynamic reloading and autodeployment, see the [Sun GlassFish Enterprise Server v2.1.1 Developer’s Guide](#).

TABLE 1–44 das-config Attributes

Attribute	Default	Description
dynamic-reload-enabled	false	(optional) If true, checks the timestamp on a .reload file at every module and application directory level, to trigger dynamic reloading.
dynamic-reload-poll-interval-in-seconds	2	(optional) Controls the polling frequency of dynamic reloading.
autodeploy-enabled	false	(optional) If true, enables autodeployment, which lets you quickly deploy applications and modules to a running Enterprise Server without performing an explicit server instance restart or a separate deployment operation.
autodeploy-polling-interval-in-seconds	2	(optional) Controls the polling frequency of autodeployment.
autodeploy-dir	autodeploy	(optional) Specifies the source directory (absolute or relative to <i>domain-dir</i>) in which autodeployment looks for deployable components.
autodeploy-verifier-enabled	false	(optional) If true, the verifier is run before autodeployment. If verification fails, deployment is not performed.
autodeploy-jsp-precompilation-enabled	false	(optional) If true, JSP pages are precompiled during autodeployment.
deploy-xml-validation	full	(optional) Specifies the type of XML validation performed on standard and Enterprise Server deployment descriptors: <ul style="list-style-type: none"> ■ full - If XML validation fails, deployment fails. ■ parsing - XML validation errors are reported but deployment occurs. ■ none - No XML validation is performed.
admin-session-timeout-in-minutes	sun-web.xml timeoutSeconds property value or web.xml session-timeout attribute value	(optional) Specifies the Administration Console timeout.

description

Contains a text description of the parent element.

Superelements

[“admin-object-resource” on page 23](#), [“appclient-module” on page 26](#),
[“connector-connection-pool” on page 42](#), [“connector-module” on page 46](#),
[“connector-resource” on page 47](#), [“custom-resource” on page 49](#), [“ejb-module” on page 57](#),

“event” on page 59, “extension-module” on page 64, “external-jndi-resource” on page 65, “j2ee-application” on page 81, “jdbc-connection-pool” on page 85, “jdbc-resource” on page 89, “lifecycle-module” on page 98, “mail-resource” on page 104, “management-rule” on page 106, “mbean” on page 109, “persistence-manager-factory-resource” on page 119, “property” on page 121, “system-property” on page 139, “transformation-rule” on page 145, “web-module” on page 155

Subelements

none - contains data

diagnostic-service

Configures the Diagnostic Service, which lets you generate a diagnostic report for troubleshooting in case of Enterprise Server malfunctioning such as exceptions, performance bottlenecks, or unexpected results.

Superelements

“config” on page 40

Subelements

The following table describes subelements for the `diagnostic-service` element.

TABLE 1-45 `diagnostic-service` Subelements

Element	Required	Description
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

The following table describes attributes for the `diagnostic-service` element.

TABLE 1-46 `diagnostic-service` Attributes

Attribute	Default	Description
<code>compute-checksum</code>	true	(optional) If true, computes a checksum of binaries.
<code>verify-config</code>	true	(optional) If true, captures the output of the <code>asadmin verify-domain-xml</code> command.
<code>capture-install-log</code>	true	(optional) If true, captures the log generated during Enterprise Server installation.
<code>capture-system-info</code>	true	(optional) If true, collects operating system level information.

TABLE 1–46 diagnostic-service Attributes *(Continued)*

Attribute	Default	Description
capture-hadb-info	true	(optional) If true, collects HADB related data. Applicable if HADB is installed and you have selected the enterprise profile. For more information about the HADB, see the <i>Sun GlassFish Enterprise Server v2.1.1 High Availability Administration Guide</i> .
capture-app-dd	true	(optional) If true, captures application deployment descriptors in plain text. If any deployment descriptors contain confidential information, you should set it to false.
min-log-level	INFO	(optional) Specifies the log level for the diagnostic report. See “ module-log-levels ” on page 112 for a description of log levels. If set to OFF, log contents are not captured.
max-log-entries	500	(optional) Specifies the maximum number of log entries captured.

domain

Defines a domain. This is the root element; there can only be one domain element in a domain.xml file.

Superelements

none

Subelements

The following table describes subelements for the domain element.

TABLE 1–47 domain Subelements

Element	Required	Description
“applications” on page 28	zero or one	Contains deployed Java EE applications, Java EE modules, and lifecycle modules.
“resources” on page 128	zero or one	Contains configured resources.
“configs” on page 41	only one	Contains configurations.
“servers” on page 134	only one	Contains server instances.
“clusters” on page 39	zero or one	Contains clusters.
“node-agents” on page 116	zero or one	Contains node agents.
“lb-configs” on page 98	zero or one	Contains load balancing configurations.
“load-balancers” on page 102	zero or one	Contains load balancers.
“system-property” on page 139	zero or more	Specifies a system property.

TABLE 1–47 domain Subelements (*Continued*)

Element	Required	Description
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

The following table describes attributes for the domain element.

TABLE 1–48 domain Attributes

Attribute	Default	Description
application-root	<i>domain-dir/applications</i>	(optional) Specifies the absolute path where deployed applications reside for this domain.
log-root	<i>domain-dir/logs</i>	(optional) Specifies where the domain’s log files are kept. The directory in which the log is kept must be writable by whatever user account the server runs as. See the “log-service” on page 102 description for details about logs.
locale	operating system default	(optional) Specifies the domain’s language.

ejb-container

Configures the EJB container. Stateless session beans are maintained in pools. Stateful session beans have session affinity and are cached. Entity beans associated with a database primary key are also cached. Entity beans not yet associated with a primary key are maintained in pools. Pooled entity beans are used to run ejbCreate() and finder methods.

Superelements

“config” on page 40

Subelements

The following table describes subelements for the ejb-container element.

TABLE 1–49 ejb-container Subelements

Element	Required	Description
“ejb-timer-service” on page 59	zero or one	Configures the EJB timer service.

TABLE 1-49 ejb-container Subelements *(Continued)*

Element	Required	Description
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

The following table describes attributes for the ejb-container element.

TABLE 1-50 ejb-container Attributes

Attribute	Default	Description
steady-pool-size	32	<p>(optional) Specifies the initial and minimum number of beans maintained in the pool. Must be 0 or greater and less than max-pool-size.</p> <p>Bean instances are removed from the pool and returned after use. The pool is replenished or cleaned up periodically to maintain this size.</p> <p>Applies to stateless session beans and entity beans.</p>
pool-resize-quantity	16	<p>(optional) Specifies the number of beans to be removed when the pool-idle-timeout-in-seconds timer expires. A cleaner thread removes any unused instances. Must be 0 or greater and less than max-pool-size. The pool is not resized below the steady-pool-size.</p> <p>Applies to stateless session beans and entity beans.</p>
max-pool-size	64	<p>(optional) Specifies the maximum number of beans that can be created to satisfy client requests. A value of 0 indicates an unbounded pool.</p> <p>Applies to stateless session beans and entity beans.</p>
cache-resize-quantity	32	<p>(optional) Specifies the number of beans to be:</p> <ul style="list-style-type: none"> ■ created if a request arrives when the pool has no available beans (subject to the max-cache-size limit) ■ passivated when the cache-idle-timeout-in-seconds timer expires and a cleaner thread removes any unused instances, or when the cache size exceeds max-cache-size. <p>Must be greater than 1 and less than max-cache-size.</p> <p>Applies to stateful session beans and entity beans.</p>
max-cache-size	512	<p>(optional) Specifies the maximum number of beans in the cache. A value of 0 indicates an unbounded cache.</p> <p>Applies to stateful session beans and entity beans.</p>

TABLE 1-50 ejb-container Attributes (Continued)

Attribute	Default	Description
pool-idle-timeout-in-seconds	600	(optional) Specifies the maximum time that a bean can remain idle in the pool. After this amount of time, the pool can remove this bean. A value of 0 specifies that idle beans can remain in the pool indefinitely. Applies to stateless session beans and entity beans.
cache-idle-timeout-in-seconds	600	(optional) Specifies the maximum time that a bean can remain idle in the cache. After this amount of time, the container can passivate this bean. A value of 0 specifies that beans never become candidates for passivation. Applies to stateful session beans and entity beans.
removal-timeout-in-seconds	5400	(optional) Specifies the amount of time that a bean can remain passivated before it is removed from the session store. A value of 0 specifies that the container does not remove inactive beans automatically. If removal-timeout-in-seconds is less than or equal to cache-idle-timeout-in-seconds, beans are removed immediately without being passivated. The session-store attribute of the “server” on page 132 element determines the location of the session store. Applies to stateful session beans.
victim-selection-policy	nru	(optional) Specifies how stateful session beans are selected for passivation. Allowed values are fifo, lru, and nru : <ul style="list-style-type: none"> ■ fifo - Selects the oldest instance. ■ lru - Selects the least recently accessed instance. ■ nru - Selects a not recently used instance.
commit-option	B	(optional) Determines which commit option is used for entity beans. Legal values are B or C.
session-store	domain-dir/session-store	(optional) Specifies the directory where passivated stateful session beans and persisted HTTP sessions are stored in the file system.

ejb-container-availability

Enables availability in the EJB container, including stateful session bean (SFSB) state persistence. If HADB is installed and you have selected the enterprise profile, session state is persisted to the HADB. For additional replicated session persistence properties you can set, see “availability-service” on page 32.

Superelements

[“availability-service” on page 32](#)

Subelements

The following table describes subelements for the `ejb-container-availability` element.

TABLE 1-51 `ejb-container-availability` Subelements

Element	Required	Description
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

The following table describes attributes for the `ejb-container-availability` element.

TABLE 1-52 `ejb-container-availability` Attributes

Attribute	Default	Description
<code>availability-enabled</code>	<code>true</code>	(optional) If set to <code>true</code> , and if availability is enabled for the server instance (see “availability-service” on page 32), high-availability features apply to all SFSBs deployed to the server instance that do not have availability disabled. All instances in a cluster should have the same availability value to ensure consistent behavior.
<code>sfsb-ha-persistence-type</code>	<code>ha</code>	(optional) Specifies the session persistence and passivation mechanism for SFSBs that have availability enabled. Allowed values are <code>file</code> (the file system) and <code>replicated</code> (other servers). If HADB is installed and you have selected the enterprise profile, you can also specify <code>ha</code> . For production environments that require session persistence, use <code>ha</code> . If set to <code>file</code> , the “ejb-container” on page 54 element’s <code>session-store</code> attribute specifies the file system location where the passivated session bean state is stored. Checkpointing to the file system is useful for internal testing but is not supported for production environments.
<code>sfsb-persistence-type</code>	<code>file</code>	(optional) Specifies the passivation mechanism for SFSBs that <i>do not</i> have availability enabled. Allowed values are <code>file</code> and <code>replicated</code> . If HADB is installed and you have selected the enterprise profile, you can also specify <code>ha</code> .
<code>sfsb-store-pool-name</code>	“availability-service” on page 32 <code>store-pool-name</code> attribute value	(optional) Specifies the jndi-name of the “jdbc-resource” on page 89 used for connections to the HADB for session persistence. Applicable if HADB is installed and you have selected the enterprise profile. For more information about setting up a connection pool and JDBC resource for the HADB, see the description of the <code>configure-ha-cluster</code> command in the Sun GlassFish Enterprise Server v2.1.1 Reference Manual .

ejb-module

Specifies a deployed EJB module.

Superelements

[“applications” on page 28](#)

Subelements

The following table describes subelements for the `ejb-module` element.

TABLE 1-53 `ejb-module` Subelements

Element	Required	Description
“description” on page 51	zero or one	Contains a text description of this element.
“web-service-endpoint” on page 157	zero or more	Configures a web service endpoint.
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

The following table describes attributes for the `ejb-module` element.

TABLE 1-54 `ejb-module` Attributes

Attribute	Default	Description
<code>name</code>	none	The name of the EJB module.
<code>location</code>	none	The location of the EJB module in the Enterprise Server file system.
<code>object-type</code>	user	(optional) Defines the type of the resource. Allowed values are: <ul style="list-style-type: none"> ■ <code>system-all</code> - A system resource for all server instances and the domain application server. ■ <code>system-admin</code> - A system resource only for the domain application server. ■ <code>system-instance</code> - A system resource for all server instances only. ■ <code>user</code> - A user resource.
<code>enabled</code>	true	(optional) Determines whether the EJB module is enabled.
<code>libraries</code>	none	(optional) Specifies an absolute or relative path to libraries specific to this module or application. A relative path is relative to <code>domain-dir/lib/applibs</code> . If the path is absolute, the path must be accessible to the domain administration server (DAS), which means it must be under <code>domain-dir</code> . To include more than one path, use a system-specific separator, such as a colon for Solaris or a semicolon for Windows. The libraries are made available to the application in the order in which they are specified.
<code>availability-enabled</code>	false	(optional) Specifies whether availability is enabled in this EJB module for SFSB checkpointing (and potentially passivation). Availability must also be enabled for the application or stand-alone EJB module during deployment. For more information about availability, see “availability-service” on page 32 .
<code>directory-deployed</code>	false	(optional) Specifies whether the application has been deployed as a directory.

ejb-timer-service

Configures the EJB timer service.

Superelements

[“ejb-container” on page 54](#)

Subelements

The following table describes subelements for the `ejb-timer-service` element.

TABLE 1-55 `ejb-timer-service` Subelements

Element	Required	Description
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

The following table describes attributes for the `ejb-timer-service` element.

TABLE 1-56 `ejb-timer-service` Attributes

Attribute	Default	Description
<code>minimum-delivery-interval-in-millis</code>	7000	(optional) Specifies the minimum time before an expiration for a particular timer can occur. This guards against extremely small timer increments that can overload the server.
<code>max-redeliveries</code>	1	(optional) Specifies the maximum number of times the EJB timer service attempts to redeliver a timer expiration due for exception or rollback.
<code>timer-datasource</code>	<code>jdbc/_TimerPool</code>	(optional) Overrides, for the cluster or server instance, the <code>cmp-resource</code> value specified in <code>sun-ejb-jar.xml</code> for the timer service system application (<code>_ejb_container_timer_app</code>).
<code>redelivery-interval-internal-in-millis</code>	5000	(optional) Specifies how long the EJB timer service waits after a failed <code>ejbTimeout</code> delivery before attempting a redelivery.

event

Defines the event that triggers the action associated with a management rule.

Predefined events are provided with the Enterprise Server. You can configure these events by changing event element attributes and properties.

You can create custom events by creating custom MBeans that implement the JMX `NotificationEmitter` interface. For more information about MBeans, see the *Sun GlassFish Enterprise Server v2.1.1 Developer's Guide* and <http://java.sun.com/javase/6/docs/api/javax/management/package-summary.html>. For information about monitor MBeans, see <http://java.sun.com/javase/6/docs/api/javax/management/monitor/package-summary.html>.

Note – If multiple rules are associated with the same event, ordering of action execution is not guaranteed.

Superelements

[“management-rule” on page 106](#)

Subelements

The following table describes subelements for the event element.

TABLE 1–57 event Subelements

Element	Required	Description
“description” on page 51	zero or one	Contains a text description of this element.
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

The following table describes attributes for the event element.

TABLE 1–58 event Attributes

Attribute	Default	Description
type	none	<p>Specifies the type of event that triggers the management rule's action. Allowed values are as follows. The <code>cluster</code>, <code>lifecycle</code>, <code>log</code>, <code>monitor</code>, <code>timer</code>, and <code>trace</code> types are predefined events provided by the Enterprise Server.</p> <p>Note – Some topics in the documentation pertain to features that are available only in domains that are configured to support clusters. Examples of domains that support clusters are domains that are created with the cluster profile or the enterprise profile. For information about profiles, see “Usage Profiles” in <i>Sun GlassFish Enterprise Server v2.1.1 Administration Guide</i>.</p> <ul style="list-style-type: none"> ■ <code>cluster</code> — A Group Management Service (GMS) event. For more information, see “group-management-service” on page 67. ■ <code>lifecycle</code> — A lifecycle event. For more information about the server life cycle, see the <i>Sun GlassFish Enterprise Server v2.1.1 Developer’s Guide</i>. ■ <code>log</code> — An event in the server log. For more information about the server log, see “log-service” on page 102. ■ <code>monitor</code> — A monitoring event, which is a change in the attribute of a monitored “mbean” on page 109. ■ <code>notification</code> — A JMX notification event. Any custom “mbean” on page 109 that implements the JMX <code>NotificationEmitter</code> interface can be a notification event. ■ <code>timer</code> — An event that occurs at a specified time. ■ <code>trace</code> — A trace event. <p>For descriptions of required and optional properties corresponding to each of these types, see the following table.</p>
level	INFO	(optional) Specifies the level at which to log the event occurrence. For information about log levels, see “ module-log-levels ” on page 112. Applicable only if record-event is set to true.
record-event	true	<p>(optional) Specifies whether the occurrence of the event is logged. If no “action” on page 23 is specified for the parent “management-rule” on page 106, the event is logged regardless of this setting.</p> <p>Note – Setting the type to <code>log</code> is different from setting record-event to true. The former specifies what the event is. The latter specifies what happens after the event occurs.</p>

Properties

The following table describes properties for the `event` element. Property names are case insensitive.

TABLE 1–59 event Properties

EventType	Property	Values	Description
cluster	name	start, stop, fail	Notifies when the GMS starts, stops, or reports failure of a server instance.

TABLE 1–59 event Properties (Continued)

EventType	Property	Values	Description
cluster	serverName	A comma-separated list of server instance names, or * for all server instances	Specifies the server instances about which GMS notifications are given.
lifecycle	name	ready, shutdown, termination	Specifies a server life cycle event. Values correspond to events defined in the com.sun.appserv.server.LifecycleEvent interface.
log	loggerNames	A comma-separated list of logger names, or * for all loggers, which is the default	(optional) Notifies when the specified loggers write messages to the server log. For a list of logger names, see “ module-log-levels ” on page 112.
log	level	A comma-separated list of log levels	(optional) Notifies when messages of the specified level are written to the server log. For information about log levels, see “ module-log-levels ” on page 112.
monitor	observedMbean	A name attribute of a user-defined “ mbean ” on page 109, or a JMX ObjectName for a system mbean	Specifies the name of the monitored MBean. Either this property or observedObject must be specified.
monitor	observedObject	An object-name attribute of a user-defined “ mbean ” on page 109, or a JMX ObjectName for a system mbean	Specifies the name of the monitored MBean. Either this property or observedMbean must be specified.
monitor	observedAttribute	An “ mbean ” on page 109 Attribute name	Specifies the monitored attribute of the monitored MBean.
monitor	monitorType	CounterMonitor, GaugeMonitor, StringMonitor	The type of monitoring of the attribute.
monitor	granularityPeriod	Time interval in seconds (long int)	(optional) Specifies the granularity at which the monitoring data should be collected.
monitor	notifyMatch	true or false	Specifies that the attribute value must match the stringToCompare value. Either this property or notifyDiffer is required if the monitor type is StringMonitor.
monitor	notifyDiffer	true or false	Specifies that the attribute value must not match the stringToCompare value. Either this property or notifyMatch is required if the monitor type is StringMonitor.
monitor	stringToCompare	A String	Specifies the value to which the attribute value is compared. Required if the monitor type is StringMonitor.

TABLE 1–59 event Properties *(Continued)*

EventType	Property	Values	Description
monitor	numberType	byte, double, float, int, long, short	Specifies the type of the numeric value being monitored. Required if the monitor is of type CounterMonitor or GaugeMonitor.
monitor	differenceMode	true or false	Specifies the difference mode flag value common to all observed MBeans. Required if the monitor is of type CounterMonitor or GaugeMonitor.
monitor	initThreshold	A positive number of the type specified by numberType	Specifies a value above which notification occurs. Required if the monitor is of type CounterMonitor.
monitor	offset	A positive number of the type specified by numberType	(optional) Specifies that the event should be re-triggered when the initThreshold value plus this offset value is reached. Applicable if the monitor is of type CounterMonitor.
monitor	modulus	A positive number of the type specified by numberType	(optional) Specifies the modulus value common to all observed MBeans. Applicable if the monitor is of type CounterMonitor.
monitor	highThreshold	A positive number of the type specified by numberType	Specifies the upper limit of the range within which notification occurs. Required if the monitor is of type GaugeMonitor.
monitor	lowThreshold	A positive number of the type specified by numberType	Specifies the lower limit of the range within which notification occurs. Required if the monitor is of type GaugeMonitor.
notification	sourceMBean	name of “mbean” on page 109	Specifies a custom MBean that implements the JMX NotificationEmitter interface. Either this property or sourceObjectName must be specified.
notification	sourceObjectName	object-name of “mbean” on page 109	Specifies a custom MBean that implements the JMX NotificationEmitter interface. Either this property or sourceMBean must be specified.
notification	type	The notification type	(optional) Specifies the notification type. If this property is specified, the action of the parent “management-rule” on page 106 is performed only if the notification type emitted is same as this property's value.
timer	dateString	Input format determined by pattern property	Begins notification at the specified date and time.
timer	pattern	SimpleDateFormat pattern	(optional) Specifies the date and time input format. The default is mm/dd/yyyy hh:mm:ss.
timer	period	Time interval in milliseconds (long int)	(optional) Notification repeats at the specified time interval.

TABLE 1–59 event Properties *(Continued)*

EventType	Property	Values	Description
timer	numberOfOccurrences	A positive number (long int)	(optional) Specifies the number of times notification occurs.
timer	message	A String	(optional) Specifies a message that is delivered as part of timer notification.
trace	name	web_component_method_entry, web_component_method_exit, ejb_component_method_entry, ejb_component_method_exit, request_start, request_end	Notifies at the specified trace point.
trace	ipAddress	An IP address	Specifies the IP address for which trace notifications are sent.
trace	callerPrincipal	A String	Specifies the caller principal for which trace notifications are sent.
trace	componentName	A String	Specifies the component name for which trace notifications are sent.

extension-module

Specifies a deployed extension module.

Superelements

[“applications” on page 28](#)

Subelements

The following table describes subelements for the `extension-module` element.

TABLE 1–60 `extension-module` Subelements

Element	Required	Description
“description” on page 51	zero or one	Contains a text description of this element.
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

The following table describes attributes for the `extension-module` element.

TABLE 1–61 extension-module Attributes

Attribute	Default	Description
name	none	The name of the extension module.
location	none	The location of the extension module in the Enterprise Server file system.
module-type	none	Specifies a String that identifies the extension module type, which the runtime uses to find the appropriate add-on container. When an extension module is registered with the Enterprise Server, the Enterprise Server specifies the module type automatically.
object-type	user	(optional) Defines the type of the resource. Allowed values are: <ul style="list-style-type: none"> ■ system-all - A system resource for all server instances and the domain application server. ■ system-admin - A system resource only for the domain application server. ■ system-instance - A system resource for all server instances only. ■ user - A user resource.
enabled	true	(optional) Determines whether the extension module is enabled.
libraries	none	(optional) Specifies an absolute or relative path to libraries specific to this module or application. A relative path is relative to <i>domain-dir/lib/applibs</i> . If the path is absolute, the path must be accessible to the domain administration server (DAS), which means it must be under <i>domain-dir</i> . To include more than one path, use a system-specific separator, such as a colon for Solaris or a semicolon for Windows. The libraries are made available to the application in the order in which they are specified.
availability-enabled	false	(optional) Specifies whether availability is enabled in this extension module. Availability must also be enabled for the application or stand-alone extension module during deployment. For more information about availability, see “ availability-service ” on page 32.
directory-deployed	false	(optional) Specifies whether the application has been deployed as a directory.

external-jndi-resource

Defines a resource that resides in an external JNDI repository. For example, a generic Java object could be stored in an LDAP server. An external JNDI factory must implement the `javax.naming.spi.InitialContextFactory` interface.

Superelements

[“resources” on page 128](#)

Subelements

The following table describes subelements for the `external-jndi-resource` element.

TABLE 1–62 external-jndi-resource Subelements

Element	Required	Description
“description” on page 51	zero or one	Contains a text description of this element.
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

The following table describes attributes for the `external-jndi-resource` element.

TABLE 1–63 external-jndi-resource Attributes

Attribute	Default	Description
jndi-name	none	Specifies the JNDI name for the resource.
jndi-lookup-name	none	Specifies the JNDI lookup name for the resource.
res-type	none	Specifies the fully qualified type of the resource.
factory-class	none	Specifies the fully qualified name of the factory class, which implements <code>javax.naming.spi.InitialContextFactory</code> . For more information about JNDI, see the Sun GlassFish Enterprise Server v2.1.1 Developer’s Guide .
object-type	user	(optional) Defines the type of the resource. Allowed values are: <ul style="list-style-type: none">■ system-all - A system resource for all server instances and the domain application server.■ system-admin - A system resource only for the domain application server.■ system-instance - A system resource for all server instances only.■ user - A user resource.
enabled	true	(optional) Determines whether this resource is enabled at runtime.

filter-config

Configures the filter class that filters alerts from notification emitters. See also “[listener-config](#)” on page 99.

Superelements

“[alert-subscription](#)” on page 26

Subelements

The following table describes subelements for the `filter-config` element.

TABLE 1–64 `filter-config` Subelements

Element	Required	Description
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

The following table describes attributes for the `filter-config` element.

TABLE 1–65 `filter-config` Attributes

Attribute	Default	Description
<code>filter-class-name</code>	none	Specifies the class name of the filter.

G

group-management-service

Configures the Group Management Service (GMS), an in-process service that provides cluster monitoring, cluster membership, and group communication services. The GMS performs the following functions:

- Notifies registered modules in an Enterprise Server instance when one or more member instances are added to or removed from a cluster, or are suspected or confirmed to have failed.
- Provides the ability to send and receive messages between a group of processes.

The GMS is built atop a configurable stack of group membership discovery and health monitoring protocols. These protocols have properties that can be changed for a given network and deployment topology. Protocols in the GMS are as follows:

- Failure detection protocol - enables its members to periodically monitor other group members to determine their availability in the group.
- Discovery protocol - is used for discovery of the group and its members.
- Verify failure protocol - verifies suspect instances by adding a verification layer to mark a failure suspicion as a confirmed failure.

Note – Some topics in the documentation pertain to features that are available only in domains that are configured to support clusters. Examples of domains that support clusters are domains that are created with the cluster profile or the enterprise profile. For information about profiles, see “[Usage Profiles](#)” in *Sun GlassFish Enterprise Server v2.1.1 Administration Guide*.

Superelements

[“config” on page 40](#)

Subelements

The following table describes subelements for the `group-management-service` element.

TABLE 1–66 `group-management-service` Subelements

Element	Required	Description
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

The following table describes attributes for the `group-management-service` element.

TABLE 1–67 `group-management-service` Attributes

Attribute	Default	Description
<code>failure-detection-max-tries</code>	3	(optional) Specifies the maximum number of monitoring attempts before the GMS confirms that a failure is suspected in the group.
<code>failure-detection-timeout-in-millis</code>	2000	(optional) Specifies the time between monitoring attempts.
<code>discovery-timeout-in-millis</code>	2000	(optional) Specifies the time that the GMS waits for discovery of other members in the group.
<code>verify-failure-timeout-in-millis</code>	1500	(optional) Specifies the timeout after which a suspected failure is marked as verified.

H

health-checker

Defines a health checker for the parent [“server-ref” on page 133](#) or [“cluster-ref” on page 38](#) element.

Superelements

[“cluster-ref” on page 38](#), [“server-ref” on page 133](#)

Subelements

none

Attributes

The following table describes attributes for the `health-checker` element.

TABLE 1–68 `health-checker` Attributes

Attribute	Default	Description
<code>url</code>	/	Specifies the URL to ping to determine the health state of a listener. This must be a relative URL.
<code>interval-in-seconds</code>	30	Specifies the interval between health checks. A value of zero means that health checking is disabled.
<code>timeout-in-seconds</code>	10	Specifies the maximum time in which a server must respond to a health check request to be considered healthy. If <code>interval-in-seconds</code> is greater than zero, <code>timeout-in-seconds</code> must be less than or equal to <code>interval-in-seconds</code> .

http-access-log

Defines an access log file for a “virtual-server” on page 146. The “access-log” on page 22 subelement of the virtual server’s parent “http-service” on page 76 element determines the access log file’s format and rotation settings.

Superelements

[“virtual-server” on page 146](#)

Subelements

none

Attributes

The following table describes attributes for the `http-access-log` element.

TABLE 1-69 http-access-log Attributes

Attribute	Default	Description
log-directory	<code> \${com.sun.aas.instanceRoot}/logs/access</code>	(optional) Specifies the location of the access log file.
iponly	true	(optional) If true, specifies that only the IP address of the user agent is listed. If false, performs a DNS lookup.

http-file-cache

Configures the HTTP file cache.

Superelements

[“http-service” on page 76](#)

Subelements

none

Attributes

The following table describes attributes for the http-file-cache element.

TABLE 1-70 http-file-cache Attributes

Attribute	Default	Description
globally-enabled	false (developer profile) true (cluster and enterprise profiles)	(optional) If true, enables the file cache.
file-caching-enabled	false (developer profile) true (cluster and enterprise profiles)	(optional) If true, enables caching of the file content if the file size exceeds the small-file-size-limit-in-bytes.
max-age-in-seconds	30	(optional) Specifies the maximum age of a file cache entry.
medium-file-size-limit-in-bytes	537600	(optional) Specifies the maximum size of a file that can be cached as a memory mapped file.
medium-file-space-in-bytes	10485760	(optional) Specifies the total size of all files that are cached as memory mapped files.

TABLE 1-70 http-file-cache Attributes *(Continued)*

Attribute	Default	Description
small-file-size-limit-in-bytes	2048	(optional) Specifies the maximum size of a file that can be read into memory.
small-file-space-in-bytes	1048576	(optional) Specifies the total size of all files that are read into memory.
file-transmission-enabled	false	(optional) If true, enables the use of <code>TransmitFileSystem</code> calls. Meaningful only for Windows.
max-files-count	1024	(optional) Specifies the maximum number of files in the file cache.
hash-init-size	0	(optional) Specifies the initial number of hash buckets.

http-listener

Defines an HTTP listen socket. The “connection-pool” on page 42 subelement of the parent “http-service” on page 76 element also configures some listen socket settings.

Superelements

[“http-service” on page 76](#)

Subelements

The following table describes subelements for the `http-listener` element.

TABLE 1-71 http-listener Subelements

Element	Required	Description
“ssl” on page 137	zero or one	Defines Secure Socket Layer (SSL) parameters.
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

The following table describes attributes for the `http-listener` element.

TABLE 1-72 http-listener Attributes

Attribute	Default	Description
<code>id</code>	none	The unique listener name. An <code>http-listener</code> name cannot begin with a number.

TABLE 1-72 http-listener Attributes (Continued)

Attribute	Default	Description
address	none	IP address of the listener. Can be in dotted-pair or IPv6 notation. Can be any (for INADDR_ANY) to listen on all IP addresses. Can be a hostname.
port	none	Port number on which the listener listens. Legal values are 1 - 65535. On UNIX, creating sockets that listen on ports 1 - 1024 requires superuser privileges. Configuring an SSL listener to listen on port 443 is standard.
external-port	none	(optional) Specifies the external port on which the connection is made.
family		(optional) Deprecated. Do not use.
blocking-enabled	false	(optional) If true, uses a blocking socket for servicing a request.
acceptor-threads	1	(optional) Specifies the number of processors in the machine. To set the number of request processing threads, use the thread-count attribute of the “request-processing” on page 126 element.
security-enabled	false	(optional) Determines whether the listener runs SSL. To turn SSL2 or SSL3 on or off and set ciphers, use an ssl subelement.
default-virtual-server	none	References the id attribute of the default “virtual-server” on page 146 for this particular listener.
server-name	none	Tells the server what to put in the host name section of any URLs it sends to the client. This affects URLs the server automatically generates; it doesn't affect the URLs for directories and files stored in the server. If your server uses an alias, the server-name should be the alias name. If a colon and port number are appended, that port is used in URLs the server sends to the client. If load balancing is enabled, use the server name of the load balancer.
redirect-port	none	(optional) If the listener is supporting non-SSL requests and a request is received for which a matching <security-constraint> requires SSL transport, the request is automatically redirected to the port number specified here. If load balancing is enabled, use the redirect port of the load balancer.
xpowered-by	true	(optional) If true, X-Powered-By headers are used according to the Servlet 2.4 and JSP 2.0 specifications.
enabled	true	(optional) Determines whether the listener is active. If set to false, any attempts to connect to the listener result in a socket exception (java.net.ConnectException). In Enterprise Server versions prior to 9.1, a listener whose enabled attribute was set to false returned a 404 response code for any requests sent to it. To achieve this behavior in the current Enterprise Server version, set the listener's enabled attribute to true, and set every associated virtual server's state to off. A “virtual-server” on page 146 lists its associated listeners in its http-listeners attribute.

TABLE 1-72 http-listener Attributes (Continued)

Attribute	Default	Description
type	default	Specifies the listener type for machines with multiple IP addresses that have separate internal and external communication. Allowed values are as follows: <ul style="list-style-type: none"> ■ internal — Used strictly for proxying by the load balancer. ■ external — Used only by user agents and not by the load balancer. ■ default — Can be used by user agents or the load balancer.

Properties

The following table describes properties for the `http-listener` element. Any of these properties can be defined as an “[http-service](#)” on page 76 property, so that it applies to all `http-listener` elements.

TABLE 1-73 http-listener Properties

Property	Default	Description
recycle-objects	true	If true, recycles internal objects instead of using the VM garbage collector.
reader-threads	0	Specifies the number of reader threads, which read bytes from the non-blocking socket.
acceptor-queue-length	4096	Specifies the length of the acceptor thread queue. Once full, connections are rejected.
reader-queue-length	4096	Specifies the length of the reader thread queue. Once full, connections are rejected.
use-nio-direct-bytebuffer	true	If true, specifies that the NIO direct <code>ByteBuffer</code> is used. In a limited resource environment, it might be faster to use non-direct Java's <code>ByteBuffer</code> by setting a value of false.
authPassthroughEnabled	false	If true, indicates that this <code>http-listener</code> element receives traffic from an SSL-terminating proxy server. Overrides the <code>authPassthroughEnabled</code> property of the parent “ http-service ” on page 76 element.
proxyHandler	<code>com.sun.enterprise.web.ProxyHandlerImpl</code>	Specifies the fully qualified class name of a custom implementation of the <code>com.sun.appserv.ProxyHandler</code> abstract class that this <code>http-listener</code> uses. Only used if the <code>authPassthroughEnabled</code> property of this <code>http-listener</code> and the parent “ http-service ” on page 76 element are both set to true. Overrides the <code>proxyHandler</code> property of the parent <code>http-service</code> element.

TABLE 1-73 http-listener Properties *(Continued)*

Property	Default	Description
proxiedProtocol	none	<p>Specifies a comma-separated list of protocols that can use the same port. Allowed values are ws/tcp (SOAP over TCP), http, https and tls.</p> <p>For example, if you set this property to http, https and set the port to 4567, you can access the port with either <code>http://host:4567/</code> or <code>https://host:4567/</code>.</p> <p>Specifying this property at the “http-service” on page 76 level overrides settings at the http-listener level. If this property is not set at either level, this feature is disabled.</p>
bufferSize	4096	Specifies the size, in bytes, of the buffer to be provided for input streams created by HTTP listeners.
connectionTimeout	30	Specifies the number of seconds HTTP listeners wait, after accepting a connection, for the request URI line to be presented.
maxKeepAliveRequests	250	Specifies the maximum number of HTTP requests that can be pipelined until the connection is closed by the server. Set this property to 1 to disable HTTP/1.0 keep-alive, as well as HTTP/1.1 keep-alive and pipelining.
traceEnabled	true	If true, enables the TRACE operation. Set this property to false to make the Enterprise Server less susceptible to cross-site scripting attacks.
cometSupport	false	<p>If true, enables Comet support for this listener.</p> <p>If your servlet or JSP page uses Comet technology, make sure it is initialized when the Enterprise Server starts up by adding the <code>load-on-startup</code> element to your <code>web.xml</code> file. For example:</p> <pre><servlet> <servlet-name>CheckIn</servlet-name> <servlet-class>CheckInServlet</servlet-class> <load-on-startup>0</load-on-startup> </servlet></pre>
compression	off	<p>Specifies use of HTTP/1.1 GZIP compression to save server bandwidth. Allowed values are:</p> <ul style="list-style-type: none"> ■ off – Disables compression. ■ on – Compresses data. ■ force – Forces data compression in all cases. ■ positive integer – Specifies the minimum amount of data required before the output is compressed. <p>If the <code>content-length</code> is not known, the output is compressed only if compression is set to on or force.</p>
compressableMimeType	text/html, text/xml, text/plain	Specifies a comma-separated list of MIME types for which HTTP compression is used.

TABLE 1-73 http-listener Properties (Continued)

Property	Default	Description
noCompressionUserAgents	empty String (regexp matching disabled)	Specifies a comma-separated list of regular expressions matching user-agents of HTTP clients for which compression should not be used.
minCompressionSize	none	Specifies the minimum size of a file when compression is applied.
crlFile	none	Specifies the location of the Certificate Revocation List (CRL) file to consult during SSL client authentication. This can be an absolute or relative file path. If relative, it is resolved against <i>domain-dir</i> . If unspecified, CRL checking is disabled.
trustAlgorithm	none	Specifies the name of the trust management algorithm (for example, PKIX) to use for certification path validation.
trustMaxCertLength	5	Specifies the maximum number of non-self-issued intermediate certificates that can exist in a certification path. This property is considered only if <code>trustAlgorithm</code> is set to PKIX. A value of zero implies that the path can only contain a single certificate. A value of -1 implies that the path length is unconstrained (there is no maximum). Setting a value less than -1 causes an exception to be thrown.
disableUploadTimeout	true	if <code>false</code> , the connection for a servlet that reads bytes slowly is closed after the <code>connectionUploadTimeout</code> is reached.
connectionUploadTimeout	5	Specifies the timeout for uploads. Applicable only if <code>disableUploadTimeout</code> is set to <code>false</code> .
uriEncoding	UTF-8	Specifies the character set used to decode the request URIs received on this HTTP listener. Must be a valid IANA character set name. Overrides the <code>uriEncoding</code> property of the parent “ http-service ” on page 76 element.

http-protocol

Configures HTTP protocol settings.

Superelements

[“http-service” on page 76](#)

Subelements

none

Attributes

The following table describes attributes for the `http-protocol` element.

TABLE 1-74 http-protocol Attributes

Attribute	Default	Description
version	HTTP/1.1	(optional) Specifies the version of the HTTP protocol used.
dns-lookup-enabled	true	(optional) If true, looks up the DNS entry for the client.
forced-type	ISO-8859-1;en; ISO-8859-1	(optional) Specifies the request type used if no MIME mapping is available that matches the file extension. The format is a semicolon-delimited string consisting of the content-type, encoding, language, and charset.
default-type	text/html; ISO-8859-1;en; ISO-8859-1	(optional) Specifies the default response type. The format is a semicolon-delimited string consisting of the content-type, encoding, language, and charset.
forced-response-type	AttributeDeprecated	(optional) Deprecated. Do not use.
default-response-type	AttributeDeprecated	(optional) Deprecated. Do not use.
ssl-enabled	true	(optional) Not implemented. Use ssl subelements of “http-listener” on page 71 elements.

http-service

Defines the HTTP service.

Superelements

[“config” on page 40](#)

Subelements

The following table describes subelements for the http-service element.

TABLE 1-75 http-service Subelements

Element	Required	Description
“access-log” on page 22	zero or one	Defines access log settings for each “http-access-log” on page 69 subelement of each “virtual-server” on page 146 .
“http-listener” on page 71	one or more	Defines an HTTP listen socket.
“virtual-server” on page 146	one or more	Defines a virtual server.
“request-processing” on page 126	zero or one	Configures request processing threads.
“keep-alive” on page 96	zero or one	Configures keep-alive threads.

TABLE 1–75 http-service Subelements (*Continued*)

Element	Required	Description
“connection-pool” on page 42	zero or one	Defines a pool of client HTTP connections.
“http-protocol” on page 75	zero or one	Configures HTTP protocol settings.
“property” on page 121	zero or more	Specifies a property or a variable.

Properties

The following table describes properties for the `http-service` element. These properties apply to all “[http-listener](#)” on page 71 subelements, except for `accessLoggingEnabled`, `accessLogBufferSize`, and `accessLogWriterInterval`, which apply to all “[virtual-server](#)” on page 146 subelements.

TABLE 1–76 http-service Properties

Property	Default	Description
<code>monitoring-cache-enabled</code>	<code>true</code>	If <code>true</code> , enables the monitoring cache.
<code>monitoring-cache-refresh-in-millis</code>	<code>5000</code>	Specifies the interval between refreshes of the monitoring cache.
<code>ssl-cache-entries</code>	<code>10000</code>	Specifies the number of SSL sessions to be cached.
<code>ssl3-session-timeout</code>	<code>86400</code>	Specifies the interval at which SSL3 sessions are cached.
<code>ssl-session-timeout</code>	<code>100</code>	Specifies the interval at which SSL2 sessions are cached.
<code>recycle-objects</code>	<code>true</code>	If <code>true</code> , recycles internal objects instead of using the VM garbage collector.
<code>reader-threads</code>	<code>0</code>	Specifies the number of reader threads, which read bytes from the non-blocking socket.
<code>acceptor-queue-length</code>	<code>4096</code>	Specifies the length of the acceptor thread queue. Once full, connections are rejected.
<code>reader-queue-length</code>	<code>4096</code>	Specifies the length of the reader thread queue. Once full, connections are rejected.
<code>use-nio-direct-bytebuffer</code>	<code>true</code>	If <code>true</code> , specifies that the NIO direct <code>ByteBuffer</code> is used. In a limited resource environment, it might be faster to use non-direct Java's <code>ByteBuffer</code> by setting a value of <code>false</code> .
<code>authPassthroughEnabled</code>	<code>false</code>	<p>If <code>true</code>, indicates that the “http-listener” on page 71 subelements receive traffic from an SSL-terminating proxy server, which is responsible for forwarding any information about the original client request (such as client IP address, SSL keysize, and authenticated client certificate chain) to the HTTP listeners using custom request headers.</p> <p>Each <code>http-listener</code> subelement can override this setting for itself.</p>

TABLE 1-76 http-service Properties *(Continued)*

Property	Default	Description
proxyHandler	com.sun.enterprise.web.ProxyHandlerImpl	<p>Specifies the fully qualified class name of a custom implementation of the com.sun.appserv.ProxyHandler abstract class, which allows a back-end application server instance to retrieve information about the original client request that was intercepted by an SSL-terminating proxy server (for example, a load balancer). An implementation of this abstract class inspects a given request for the custom request headers through which the proxy server communicates the information about the original client request to the Enterprise Server instance, and returns that information to its caller.</p> <p>The default implementation reads the client IP address from an HTTP request header named <code>Proxy-ip</code>, the SSL keysize from an HTTP request header named <code>Proxy-keysize</code>, and the SSL client certificate chain from an HTTP request header named <code>Proxy-auth-cert</code>. The <code>Proxy-auth-cert</code> value must contain the BASE-64 encoded client certificate chain without the BEGIN CERTIFICATE and END CERTIFICATE boundaries and with <code>\n</code> replaced with <code>%d\n</code>.</p> <p>Only used if <code>authPassthroughEnabled</code> is set to <code>true</code>. Each “http-listener” on page 71 subelement can override the <code>proxyHandler</code> setting for itself.</p>
proxiedProtocol	none	<p>Specifies a comma-separated list of protocols that can use the same port. Allowed values are <code>ws/tcp</code> (SOAP over TCP), <code>http</code>, <code>https</code> and <code>tls</code>.</p> <p>For example, if you set this property to <code>http,https</code> and the port is 4567, you can access the port with either <code>http://host:4567</code> or <code>https://host:4567</code>.</p> <p>Specifying this property at the http-service level overrides settings at the “http-listener” on page 71 level. If this property is not set at either level, this feature is disabled.</p>
bufferSize	4096	Specifies the size, in bytes, of the buffer to be provided for input streams created by HTTP listeners.
connectionTimeout	30	Specifies the number of seconds HTTP listeners wait, after accepting a connection, for the request URI line to be presented.
maxKeepAliveRequests	250	Specifies the maximum number of HTTP requests that can be pipelined until the connection is closed by the server. Set this property to 1 to disable HTTP/1.0 keep-alive, as well as HTTP/1.1 keep-alive and pipelining.
traceEnabled	true	If <code>true</code> , enables the TRACE operation. Set this property to <code>false</code> to make the Enterprise Server less susceptible to cross-site scripting attacks.
accessLoggingEnabled	<p><code>false</code> (developer and cluster profiles)</p> <p><code>true</code> (enterprise profile)</p>	If <code>true</code> , enables access logging for all “ virtual-server ” on page 146 subelements that do not specify this property. If <code>false</code> , disables access logging for all <code>virtual-server</code> subelements that do not specify this property.

TABLE 1-76 http-service Properties *(Continued)*

Property	Default	Description
accessLogBufferSize	32768	Specifies the size, in bytes, of the buffer where access log calls are stored. If the value is less than 5120, a warning message is issued, and the value is set to 5120.
accessLogWriterInterval	300	Specifies the number of seconds before the log is written to the disk. The access log is written when the buffer is full or when the interval expires. If the value is 0, the buffer is always written even if it is not full. This means that each time the server is accessed, the log message is stored directly to the file.
sso-enabled	false (developer and cluster profiles) true (enterprise profile)	If true, single sign-on is enabled by default for all web applications on all virtual servers on this server instance that are configured for the same realm. If false, single sign-on is disabled by default for all virtual servers, and users must authenticate separately to every application on each virtual server. The sso-enabled property setting of the “virtual-server” on page 146 element overrides this setting for an individual virtual server. At the http-service level, you cannot change the sso-max-inactive-seconds and sso-reap-interval-seconds values from their defaults. However, you can change these values at the virtual-server level.
disableUploadTimeout	true	if false, the connection for a servlet that reads bytes slowly is closed after the connectionUploadTimeout is reached.
connectionUploadTimeout	5	Specifies the timeout for uploads. Applicable only if disableUploadTimeout is set to false.
uriEncoding	UTF-8	Specifies the character set used to decode the request URIs received on “http-listener” on page 71 subelements that do not define this property. Must be a valid IANA character set name.

iiop-listener

Defines an IIOP listen socket. To enable SSL for this listener, include an `ssl` subelement.

Superelements

[“iiop-service” on page 80](#)

Subelements

The following table describes subelements for the `iiop-listener` element.

TABLE 1-77 *iiop-listener* Subelements

Element	Required	Description
“ssl” on page 137	zero or one	Defines SSL parameters.
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

The following table describes attributes for the *iiop-listener* element.

TABLE 1-78 *iiop-listener* Attributes

Attribute	Default	Description
<code>id</code>	<code>none</code>	The listener name. An <i>iiop-listener</i> name cannot begin with a number.
<code>address</code>	<code>none</code>	IP address of the listener. Can be in dotted-pair or IPv6 notation, or just a name.
<code>port</code>	<code>1072</code>	(optional) Port number for the listener. Legal values are 1 - 65535. On UNIX, creating sockets that listen on ports 1 - 1024 requires superuser privileges.
<code>security-enabled</code>	<code>false</code>	(optional) Determines whether the listener runs SSL. To turn SSL2 or SSL3 on or off and set ciphers, use an <code>ssl</code> element.
<code>enabled</code>	<code>true</code>	(optional) Determines whether the listener is active.

iiop-service

Defines the IIOP service.

Superelements

“config” on page 40

Subelements

The following table describes subelements for the *iiop-service* element.

TABLE 1-79 *iiop-service* Subelements

Element	Required	Description
“orb” on page 117	only one	Configures the ORB.
“ssl-client-config” on page 138	zero or one	Defines SSL parameters for the ORB.
“iiop-listener” on page 79	zero or more	Defines an IIOP listen socket.

Attributes

The following table describes attributes for the `iiop-service` element.

TABLE 1-80 `iiop-service` Attributes

Attribute	Default	Description
<code>client-authentication-required</code>	<code>false</code>	(optional) If true, the server rejects unauthenticated requests and inserts an authentication-required bit in IORs sent to clients.

J

j2ee-application

Specifies a deployed Java EE application.

Superelements

[“applications” on page 28](#)

Subelements

The following table describes subelements for the `j2ee-application` element.

TABLE 1-81 `j2ee-application` Subelements

Element	Required	Description
“description” on page 51	zero or one	Contains a text description of this element.
“web-service-endpoint” on page 157	zero or more	Configures a web service endpoint.
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

The following table describes attributes for the `j2ee-application` element.

TABLE 1-82 `j2ee-application` Attributes

Attribute	Default	Description
<code>name</code>	<code>none</code>	The name of the application.

TABLE 1-82 j2ee-application Attributes (Continued)

Attribute	Default	Description
location	none	The location of the application in the Enterprise Server file system.
object-type	user	(optional) Defines the type of the resource. Allowed values are: <ul style="list-style-type: none"> ■ system-all - A system resource for all server instances and the domain application server. ■ system-admin - A system resource only for the domain application server. ■ system-instance - A system resource for all server instances only. ■ user - A user resource.
enabled	true	(optional) Determines whether the application is enabled.
libraries	none	(optional) Specifies an absolute or relative path to libraries specific to this module or application. A relative path is relative to <i>domain-dir/lib/applibs</i> . If the path is absolute, the path must be accessible to the domain administration server (DAS), which means it must be under <i>domain-dir</i> . To include more than one path, use a system-specific separator, such as a colon for Solaris or a semicolon for Windows. The libraries are made available to the application in the order in which they are specified.
availability-enabled	false	(optional) Specifies whether availability is enabled in this Java EE application for HTTP session persistence and SFSB checkpointing (and potentially passivation). Availability must also be enabled for the application during deployment. For more information about availability, see “ availability-service ” on page 32.
directory-deployed	false	(optional) Specifies whether the application has been deployed as a directory.
java-web-start-enabled	true	(optional) Specifies whether Java Web Start access is permitted for application clients in this application.

jacc-provider

Specifies a Java Authorization Contract for Containers (JACC) provider for pluggable authorization.

Superelements

[“security-service” on page 131](#)

Subelements

The following table describes subelements for the `jacc-provider` element.

TABLE 1–83 jacc-provider Subelements

Element	Required	Description
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

The following table describes attributes for the `jacc-provider` element.

TABLE 1–84 jacc-provider Attributes

Attribute	Default	Description
<code>name</code>	<code>default</code>	Specifies the name of the JACC provider.
<code>policy-provider</code>	<code>com.sun.enterprise.security.provider.PolicyWrapper</code>	Corresponds to and can be overridden by the system property <code>javax.security.jacc.policy.provider</code> .
<code>policy-configuration-factory-provider</code>	<code>com.sun.enterprise.security.provider.PolicyConfigurationFactoryImpl</code>	Corresponds to and can be overridden by the system property <code>javax.security.jacc.PolicyConfigurationFactory.provider</code> .

java-config

Specifies Java Virtual Machine (JVM) configuration parameters.

Superelements

“config” on page 40

Subelements

The following table describes subelements for the `java-config` element.

TABLE 1–85 java-config Subelements

Element	Required	Description
“profiler” on page 121	zero or one	Configures a profiler for use with the Enterprise Server.
“jvm-options” on page 96	zero or more	Contains JVM command line options.
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

The following table describes attributes for the `java-config` element.

TABLE 1-86 java-config Attributes

Attribute	Default	Description
java-home	none	The path to the directory where the JDK is installed.
debug-enabled	false	(optional) If true, the server starts up in debug mode ready for attachment with a JPDA-based debugger.
debug-options	<code>-Xdebug -Xrunjdwp:transport=dt_socket,server=y,suspend=n</code>	(optional) Specifies JPDA (Java Platform Debugger Architecture) options. A list of debugging options is available at http://java.sun.com/products/jpda/doc/connninv.html#Invocation . For more information about debugging, see the <i>Sun GlassFish Enterprise Server v2.1.1 Developer's Guide</i> .
rmic-options	<code>-iiop -poa -alwaysgenerate -keepgenerated -g</code>	(optional) Specifies options passed to the RMI compiler at application deployment time. The <code>-keepgenerated</code> option saves generated source for stubs and ties. For details about the <code>rmic</code> command, see http://java.sun.com/javase/6/docs/technotes/tools/solaris/rmic.html .
javac-options	<code>-g</code>	(optional) Specifies options passed to the Java compiler at application deployment time.
classpath-prefix	none	(optional) Specifies a prefix for the server classpath. Only prefix this classpath to override Enterprise Server classes. Use this attribute with caution.
classpath-suffix	none	(optional) Specifies a suffix for the server classpath.
server-classpath	none	(optional) Specifies additions to the server classpath. Supported for backward compatibility. Use <code>classpath-suffix</code> instead.
system-classpath	JVM classes	(optional) Specifies additions to the system classpath, which is supplied to the JVM at server startup. These classes are loaded by the System Classloader. Note – Do not remove the default path.
native-library-path-prefix	none	(optional) Specifies a prefix for the native library path. The native library path is the automatically constructed concatenation of the Enterprise Server installation relative path for its native shared libraries, the standard JRE native library path, the shell environment setting (<code>LD_LIBRARY_PATH</code> on UNIX), and any path specified in the <code>profiler</code> element. Since this is synthesized, it does not appear explicitly in the server configuration.
native-library-path-suffix	none	(optional) Specifies a suffix for the native library path.
bytecode-preprocessors	none	(optional) A comma separated list of class names, each of which must implement the <code>com.sun.appserv.BytecodePreprocessor</code> interface. Each of the specified preprocessor classes is called in the order specified.

TABLE 1-86 java-config Attributes *(Continued)*

Attribute	Default	Description
env-classpath-ignored	true	<p>(optional) If <code>false</code>, the CLASSPATH environment variable is read and appended to the Enterprise Server classpath. The CLASSPATH environment variable is added after the <code>classpath-suffix</code>, at the very end.</p> <p>For a development environment, this value should be set to <code>false</code>. To prevent environment variable side effects in a production environment, set this value to <code>true</code>.</p>

jdbc-connection-pool

Defines the properties that are required for creating a JDBC connection pool.

Superelements

[“resources” on page 128](#)

Subelements

The following table describes subelements for the `jdbc-connection-pool` element.

TABLE 1-87 jdbc-connection-pool Subelements

Element	Required	Description
“description” on page 51	zero or one	Contains a text description of this element.
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

The following table describes attributes for the `jdbc-connection-pool` element. Changing the following attributes requires a server restart: `datasource-classname`, `associate-with-thread`, `lazy-connection-association`, and `lazy-connection-enlistment`.

TABLE 1-88 jdbc-connection-pool Attributes

Attribute	Default	Description
<code>name</code>	none	Specifies the name of the connection pool. A “jdbc-resource” on page 89 element’s <code>pool-name</code> attribute refers to this name.
<code>datasource-classname</code>	none	Specifies the class name of the associated vendor-supplied data source. This class must implement <code>javax.sql.DataSource</code> , <code>javax.sql.XADatasource</code> , <code>javax.sql.ConnectionPoolDataSource</code> , or a combination.

TABLE 1-88 `jdbc-connection-pool` Attributes (Continued)

Attribute	Default	Description
<code>res-type</code>	<code>javax.sql.DataSource</code>	(optional) Specifies the interface the data source class implements. The value of this attribute can be <code>javax.sql.DataSource</code> , <code>javax.sql.XADatasource</code> , or <code>javax.sql.ConnectionPoolDataSource</code> . If the value is not one of these interfaces, the default is used. An error occurs if this attribute has a legal value and the indicated interface is not implemented by the data source class.
<code>steady-pool-size</code>	8	(optional) Specifies the initial and minimum number of connections maintained in the pool.
<code>max-pool-size</code>	32	(optional) Specifies the maximum number of connections that can be created to satisfy client requests.
<code>max-wait-time-in-millis</code>	60000	(optional) Specifies the amount of time, in milliseconds, that the caller is willing to wait for a connection. If 0, the caller is blocked indefinitely until a resource is available or an error occurs.
<code>pool-resize-quantity</code>	2	(optional) Specifies the number of idle connections to be destroyed if the existing number of connections is above the <code>steady-pool-size</code> (subject to the <code>max-pool-size</code> limit). This is enforced periodically at the <code>idle-timeout-in-seconds</code> interval. An idle connection is one that has not been used for a period of <code>idle-timeout-in-seconds</code> . When the pool size reaches <code>steady-pool-size</code> , connection removal stops.
<code>idle-timeout-in-seconds</code>	300	(optional) Specifies the maximum time that a connection can remain idle in the pool. After this amount of time, the pool can close this connection.
<code>transaction-isolation-level</code>	default JDBC driver isolation level	(optional) Specifies the transaction isolation level on the pooled database connections. Allowed values are <code>read-uncommitted</code> , <code>read-committed</code> , <code>repeatable-read</code> , or <code>serializable</code> . Applications that change the isolation level on a pooled connection programmatically risk polluting the pool, which can lead to errors. See <code>is-isolation-level-guaranteed</code> for more details.
<code>is-isolation-level-guaranteed</code>	true	(optional) Applicable only when <code>transaction-isolation-level</code> is explicitly set. If true, every connection obtained from the pool is guaranteed to have the desired isolation level. This might impact performance on some JDBC drivers. Only set this attribute to false if you are certain that the hosted applications do not return connections with altered isolation levels.
<code>is-connection-validation-required</code>	false	(optional) Specifies whether connections have to be validated before being given to the application. If a resource's validation fails, it is destroyed, and a new resource is created and returned.

TABLE 1-88 `jdbc-connection-pool` Attributes *(Continued)*

Attribute	Default	Description
<code>connection-validation-method</code>	<code>auto-commit</code>	(optional) Legal values are as follows: <ul style="list-style-type: none">■ <code>auto-commit</code> (default), which uses <code>Connection.setAutoCommit(Connection.getAutoCommit())</code>■ <code>meta-data</code>, which uses <code>Connection.getMetaData()</code>■ <code>table</code>, which performs a query on a table specified in the <code>validation-table-name</code> attribute
<code>validation-table-name</code>	<code>none</code>	(optional) Specifies the table name to be used to perform a query to validate a connection. This parameter is mandatory if and only if <code>connection-validation-method</code> is set to <code>table</code> .
<code>fail-all-connections</code>	<code>false</code>	(optional) If <code>true</code> , closes all connections in the pool if a single validation check fails. This parameter is mandatory if and only if <code>is-connection-validation-required</code> is set to <code>true</code> .
<code>non-transactional-connections</code>	<code>false</code>	(optional) If <code>true</code> , non-transactional connections can be made to the JDBC connection pool. These connections are not automatically enlisted with the transaction manager.
<code>allow-non-component-callers</code>	<code>false</code>	(optional) If <code>true</code> , non-Java EE components, such as servlet filters, lifecycle modules, and third party persistence managers, can use this JDBC connection pool. The returned connection is automatically enlisted with the transaction context obtained from the transaction manager. Standard Java EE components can also use such pools. Connections obtained by non-component callers are not automatically closed at the end of a transaction by the container. They must be explicitly closed by the caller.
<code>connection-leak-timeout-in-seconds</code>	<code>0</code>	Detects potential connection leaks by the application. A connection that is not returned back to the pool by the application within the specified period is assumed to be potentially leaking, and a stack trace of the caller is logged. A zero value disables leak detection. A nonzero value enables leak tracing.
<code>connection-leak-reclaim</code>	<code>false</code>	If <code>true</code> , the pool will reclaim a connection after <code>connection-leak-timeout-in-seconds</code> occurs.
<code>connection-creation-retry-attempts</code>	<code>0</code>	Specifies the number of attempts to create a new connection.
<code>connection-creation-retry-interval-in-seconds</code>	<code>10</code>	Specifies the time interval between attempts to create a connection when <code>connection-creation-retry-attempts</code> is greater than <code>0</code> .
<code>validate-atmost-once-period-in-seconds</code>	<code>0</code>	Specifies the time interval within which a connection is validated at most once. Minimizes the number of validation calls.
<code>statement-timeout-in-seconds</code>	<code>-1</code>	Sets the query timeout property of a statement to enable termination of abnormally long running queries. The default value of <code>-1</code> disables this feature.
<code>lazy-connection-enlistment</code>	<code>false</code>	If <code>true</code> , a connection is not enlisted in a transaction until it is used. If <code>false</code> , any connection object available to a transaction is enlisted in the transaction.

TABLE 1–88 `jdbc-connection-pool` Attributes (Continued)

Attribute	Default	Description
<code>lazy-connection-association</code>	<code>false</code>	If <code>true</code> , a physical connection is not associated with a logical connection until it is used. If <code>false</code> , a physical connection is associated with a logical connection even before it is used.
<code>associate-with-thread</code>	<code>false</code>	If <code>true</code> , allows a connection to be saved as a <code>ThreadLocal</code> in the calling thread. This connection gets reclaimed only when the calling thread dies or when the calling thread is not in use and the pool has run out of connections.
<code>match-connections</code>	<code>false</code>	If <code>true</code> , enables connection matching. You can set to <code>false</code> if connections are homogeneous.
<code>max-connection-usage-count</code>	<code>0</code>	Specifies the number of times a connection is reused by the pool, after which it is closed. A zero value disables this feature.
<code>wrap-jdbc-objects</code>	<code>false</code>	If <code>true</code> , the application returns wrapped JDBC objects for <code>Statement</code> , <code>PreparedStatement</code> , <code>CallableStatement</code> , <code>ResultSet</code> , and <code>DatabaseMetaData</code> .

Properties

Most JDBC drivers allow use of standard property lists to specify the user, password, and other resource configuration information. Although properties are optional with respect to the Enterprise Server, some properties might be necessary for most databases. For details, see the JDBC 4.0 Standard Extension API.

When properties are specified, they are passed to the vendor's data source class (specified by the `datasource-classname` attribute) as is using `setName(value)` methods.

The `user` and `password` properties are used as the default principal if container managed authentication is specified and a `default-resource-principal` is not found in the application deployment descriptors.

The following table describes some common properties for the `jdbc-connection-pool` element.

Changing JDBC driver properties requires a server restart.

TABLE 1–89 `jdbc-connection-pool` Properties

Property	Description
<code>user</code>	Specifies the user name for connecting to the database.
<code>password</code>	Specifies the password for connecting to the database.
<code>databaseName</code>	Specifies the database for this connection pool.
<code>serverName</code>	Specifies the database server for this connection pool.

TABLE 1-89 `jdbc-connection-pool` Properties *(Continued)*

Property	Description
<code>port</code>	Specifies the port on which the database server listens for requests.
<code>networkProtocol</code>	Specifies the communication protocol.
<code>roleName</code>	Specifies the initial SQL role name.
<code>datasourceName</code>	Specifies an underlying XADatasource, or a ConnectionPoolDataSource if connection pooling is done.
<code>description</code>	Specifies a text description.
<code>url</code>	Specifies the URL for this connection pool. Although this is not a standard property, it is commonly used.
<code>LazyConnection Enlistment</code>	Deprecated. Use the equivalent attribute.
<code>LazyConnection Association</code>	Deprecated. Use the equivalent attribute.
<code>AssociateWithThread</code>	Deprecated. Use the equivalent attribute.
<code>MatchConnections</code>	Deprecated. Use the equivalent attribute.

jdbc-resource

Defines a JDBC (`javax.sql.DataSource`) resource.

Superelements

[“resources” on page 128](#)

Subelements

The following table describes subelements for the `jdbc-resource` element.

TABLE 1-90 `jdbc-resource` Subelements

Element	Required	Description
“description” on page 51	zero or one	Contains a text description of this element.
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

The following table describes attributes for the `jdbc-resource` element.

TABLE 1–91 jdbc-resource Attributes

Attribute	Default	Description
jndi-name	none	Specifies the JNDI name for the resource.
pool-name	none	Specifies the name of the associated “ jdbc-connection-pool ” on page 85.
object-type	user	(optional) Defines the type of the resource. Allowed values are: <ul style="list-style-type: none"> ■ system-all - A system resource for all server instances and the domain application server. ■ system-admin - A system resource only for the domain application server. ■ system-instance - A system resource for all server instances only. ■ user - A user resource.
enabled	true	(optional) Determines whether this resource is enabled at runtime.

jms-availability

Enables availability in the Sun GlassFish Message Queue cluster that comprises the Java Message Service (JMS). Messages are saved to the HADB. The HADB must be installed and the enterprise profile must be selected. You must enable availability for Enterprise Server instances before you can enable availability for the corresponding Message Queue brokers.

Note – Individual applications and modules cannot control or override JMS availability.

Note – Some topics in the documentation pertain to features that are available only in domains that are configured to support clusters. Examples of domains that support clusters are domains that are created with the cluster profile or the enterprise profile. For information about profiles, see “[Usage Profiles](#)” in *Sun GlassFish Enterprise Server v2.1.1 Administration Guide*.

Superelements

“[availability-service](#)” on page 32

Subelements

The following table describes subelements for the jms-availability element.

TABLE 1–92 jms-availability Subelements

Element	Required	Description
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

The following table describes attributes for the jms-availability element.

TABLE 1–93 jms-availability Attributes

Attribute	Default	Description
availability-enabled	false	(optional) If set to true, and if availability is enabled for the Enterprise Server instance (see “availability-service” on page 32), high-availability is enabled for the Message Queue cluster associated with the Enterprise Server cluster. All instances in an Enterprise Server cluster should have the same availability settings to ensure consistent behavior.
mq-store-pool-name	“availability-service” on page 32 store-pool-name attribute value	(optional) Specifies the jndi-name of the “jdbc-resource” on page 89 used for connections to the HADB for the Message Queue cluster. Applicable if HADB is installed and you have selected the enterprise profile. For more information about setting up a connection pool and JDBC resource for the HADB, see the description of the configure-ha-cluster command in the <i>Sun GlassFish Enterprise Server v2.1.1 Reference Manual</i> .

jms-host

Configures the host of the built-in Java Message Service (JMS) that is managed by the Enterprise Server.

Superelements

“jms-service” on page 92

Subelements

The following table describes subelements for the jms-host element.

TABLE 1–94 jms-host Subelements

Element	Required	Description
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

The following table describes attributes for the jms-host element.

TABLE 1–95 jms-host Attributes

Attribute	Default	Description
name	none	Specifies the name of the JMS host.
host	<i>machine-name</i>	(optional) Specifies the host name of the JMS host.
port	7676	(optional) Specifies the port number used by the JMS provider.
admin-user-name	admin	(optional) Specifies the administrator user name for the JMS provider.
admin-password	admin	(optional) Specifies the administrator password for the JMS provider.

jms-service

Configures the built-in Java Message Service (JMS) that is managed by the Enterprise Server.

Superelements

[“config” on page 40](#)

Subelements

The following table describes subelements for the `jms-service` element.

TABLE 1–96 jms-service Subelements

Element	Required	Description
“jms-host” on page 91	zero or more	Specifies a host.
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

The following table describes attributes for the `jms-service` element.

TABLE 1–97 jms-service Attributes

Attribute	Default	Description
init-timeout-in-seconds	60	(optional) Specifies the amount of time the server instance waits at startup for its configured default JMS host to respond. If there is no response, startup is aborted. If set to 0, the server instance waits indefinitely.

TABLE 1-97 jms-service Attributes (Continued)

Attribute	Default	Description
type	EMBEDDED (DAS) or LOCAL (other server instances)	<p>Specifies the type of JMS service:</p> <ul style="list-style-type: none"> ■ EMBEDDED means the JMS provider is started in the same JVM as the Enterprise Server, and the networking stack is bypassed. Lazy initialization starts the default embedded broker on the first access of JMS services rather than at Enterprise Server startup. EMBEDDED mode is not a supported configuration for a cluster. ■ LOCAL means the JMS provider is started along with the Enterprise Server. The LOCAL setting implicitly sets up a 1:1 relationship between an Enterprise Server instance and a Message Queue broker. When you create an Enterprise Server cluster, a Message Queue cluster is automatically created as well. During cluster creation, each instance in the Enterprise Server cluster is automatically configured with a broker in the Message Queue cluster, and a unique broker port is determined. ■ REMOTE means the JMS provider is remote and is not started by the Enterprise Server.
start-args	none	(optional) Specifies the string of arguments supplied for startup of the corresponding JMS instance.
default-jms-host	none	Specifies the name of the default “ jms-host ” on page 91. If type is set to LOCAL, this jms-host is automatically started at Enterprise Server startup.
reconnect-interval-in-seconds	5 (developer profile) 60 (cluster and enterprise profiles)	(optional) Specifies the interval between reconnect attempts.
reconnect-attempts	3	(optional) Specifies the number of reconnect attempts.
reconnect-enabled	true	<p>(optional) If true, reconnection is enabled. The JMS service automatically tries to reconnect to the JMS provider when the connection is broken.</p> <p>When the connection is broken, depending on the message processing stage, the <code>onMessage()</code> method might not be able to complete successfully or the transaction might be rolled back due to a JMS exception. When the JMS service reestablishes the connection, JMS message redelivery semantics apply.</p>
addresslist-behavior	random	(optional) Specifies whether the reconnection logic selects the broker from the <code>imqAddressList</code> in a random or sequential (priority) fashion.
addresslist-iterations	3	(optional) Specifies the number of times the reconnection logic iterates over the <code>imqAddressList</code> if <code>addresslist-behavior</code> is set to PRIORITY.
mq-scheme	mq	(optional) Specifies the scheme for establishing connection with the broker. For example, specify http for connecting to the broker over HTTP.

TABLE 1–97 jms-service Attributes (Continued)

Attribute	Default	Description
mq-service	jms	(optional) Specifies the type of broker service. If a broker supports SSL, the type of service can be <code>ssljms</code> .

Properties

The following table describes properties for the `jms-service` element.

TABLE 1–98 jms-service Properties

Property	Default	Description
instance-name	imqbroker	Specifies the full Sun GlassFish Message Queue broker instance name.
instance-name-suffix	none	Specifies a suffix to add to the full Message Queue broker instance name. The suffix is separated from the instance name by an underscore character (<code>_</code>). For example, if the instance name is <code>imqbroker</code> , appending the suffix <code>xyz</code> changes the instance name to <code>imqbroker_xyz</code> .
append-version	false	If <code>true</code> , appends the major and minor version numbers, preceded by underscore characters (<code>_</code>), to the full Message Queue broker instance name. For example, if the instance name is <code>imqbroker</code> , appending the version numbers changes the instance name to <code>imqbroker_8_0</code> .
user-name	guest	Specifies the user name for creating the JMS connection. Needed only if the default username/password of guest/guest is not available in the broker.
password	guest	Specifies the password for creating the JMS connection. Needed only if the default username/password of guest/guest is not available in the broker.

jmx-connector

Configures a JSR 160/255 compliant remote JMX connector, which handles the JMX communication between the domain administration server, the node agents, and the remote server instances. This JMX connector also handles JMX communication between an external management client and the domain administration server.

Only the system JMX connector is started by the server processes at startup. Do not configure additional JMX connectors.

Superelements

[“admin-service” on page 24](#), [“node-agent” on page 115](#)

Subelements

The following table describes subelements for the `jmx-connector` element.

TABLE 1–99 jmx-connector Subelements

Element	Required	Description
“ssl” on page 137	zero or one	Defines SSL parameters.
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

The following table describes attributes for the `jmx-connector` element.

TABLE 1–100 jmx-connector Attributes

Attribute	Default	Description
name	none	Specifies the name of the connector used by the designated system JMX connector for JMX communication between server instances. Do not modify this name.
protocol	rmi_jrmp	(optional) Specifies the protocol that this JMX connector supports. The only supported protocol is <code>rmi_jrmp</code> . Do not modify this value.
address	0.0.0.0	Specifies the IP address of the naming service where the JMX connector server stub is registered. This is not the port of the server socket that does the actual JMX communication. This is the address of the network interface where the RMI registry is started. If your system has multiple network interfaces, modify this value so that only a particular interface is selected.
port	8686 (DAS, all profiles; server instance, developer profile) 38686 (server instances, cluster and enterprise profiles)	Specifies the port number on which the naming service (RMI registry) listens for RMI client connections. The only use of this naming service is to download the RMI stubs. If the default port is occupied, a free port is used. Legal values are 1 - 65535. On UNIX, creating sockets that listen on ports 1 - 1024 requires superuser privileges.
auth-realm-name	admin-realm	Specifies the name of an “auth-realm” on page 29 subelement of the “security-service” on page 131 element for the server instance that is running this JMX connector’s server end. Note that this is a dedicated administration security realm.
security-enabled	false (developer profile) true (cluster and enterprise profiles)	(optional) Determines whether JMX communication is encrypted.

jvm-options

Contains JVM command line options, for example:

```
<jvm-options>-Xdebug -Xmx128m</jvm-options>
```

For information about JVM options, see <http://java.sun.com/docs/hotspot/VMOPTIONS.html>.

Superelements

[“java-config” on page 83](#), [“profiler” on page 121](#)

Subelements

none - contains data

K

keep-alive

Configures keep-alive threads.

Superelements

[“http-service” on page 76](#)

Subelements

none

Attributes

The following table describes attributes for the `keep-alive` element.

TABLE 1-101 keep-alive Attributes

Attribute	Default	Description
thread-count	1	(optional) Specifies the number of keep-alive threads. The value must be 1 or greater.

TABLE 1-101 keep-alive Attributes *(Continued)*

Attribute	Default	Description
max-connections	256	(optional) Specifies the maximum number of keep-alive connections. A value of 0 means requests are always rejected. A value of -1 sets no limit to the number of keep-alive connections.
timeout-in-seconds	60	(optional) Specifies the maximum time for which a keep alive connection is kept open. A value of 0 or less means keep alive connections are kept open indefinitely.

L

lb-config

Defines a load balancer configuration, which can be referenced by a physical “load-balancer” on page 100.

Note – Some topics in the documentation pertain to features that are available only in domains that are configured to support clusters. Examples of domains that support clusters are domains that are created with the cluster profile or the enterprise profile. For information about profiles, see “Usage Profiles” in *Sun GlassFish Enterprise Server v2.1.1 Administration Guide*.

Superelements

“lb-configs” on page 98

Subelements

The following table describes subelements for the lb-config element.

TABLE 1-102 lb-config Subelements

Element	Required	Description
“cluster-ref” on page 38	zero or more; zero if a server-ref is defined	References a cluster. This element contains some attributes related to load balancing.
“server-ref” on page 133	zero or more; zero if a cluster-ref is defined	References a server instance that does not belong to a cluster. The referenced “server” on page 132 element contains some attributes related to load balancing.
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

The following table describes attributes for the `lb-config` element.

TABLE 1–103 `lb-config` Attributes

Attribute	Default	Description
<code>name</code>	<code>none</code>	Specifies the name of the load balancer configuration.
<code>response-timeout-in-seconds</code>	<code>60</code>	(optional) Specifies the time within which a server must return a response or it is considered unhealthy.
<code>https-routing</code>	<code>false</code>	(optional) If <code>true</code> , HTTPS requests to the load balancer result in HTTPS requests to the server. If <code>false</code> , HTTPS requests to the load balancer result in HTTP requests to the server.
<code>reload-poll-interval-in-seconds</code>	<code>60</code>	(optional) Specifies the interval between checks for changes to the load balancer configuration file (<code>loadbalancer.xml</code>). When changes are detected, the file is reloaded. A value of zero disables reloading.
<code>monitoring-enabled</code>	<code>false</code>	(optional) If <code>true</code> , enables monitoring of load balancing.

lb-configs

Contains load balancer configurations.

Superelements

[“domain” on page 53](#)

Subelements

The following table describes subelements for the `lb-configs` element.

TABLE 1–104 `lb-configs` Subelements

Element	Required	Description
“lb-config” on page 97	zero or more	Defines a load balancer configuration.

lifecycle-module

Specifies a deployed lifecycle module. For more information about lifecycle modules, see the [Sun GlassFish Enterprise Server v2.1.1 Developer’s Guide](#).

Superelements

[“applications” on page 28](#)

Subelements

The following table describes subelements for the `lifecycle-module` element.

TABLE 1-105 `lifecycle-module` Subelements

Element	Required	Description
“description” on page 51	zero or one	Contains a text description of this element.
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

The following table describes attributes for the `lifecycle-module` element.

TABLE 1-106 `lifecycle-module` Attributes

Attribute	Default	Description
name	none	The name of the lifecycle module.
class-name	none	The fully qualified name of the lifecycle module’s class file, which must implement the <code>com.sun.appserv.server.LifecycleListener</code> interface.
classpath	value of application - root attribute of “domain” on page 53 element	(optional) The classpath for the lifecycle module. Specifies where the module is located.
load-order	none	(optional) Determines the order in which lifecycle modules are loaded at startup. Modules with smaller integer values are loaded sooner. Values can range from 101 to the operating system’s MAXINT. Values from 1 to 100 are reserved.
is-failure-fatal	false	(optional) Determines whether the server is shut down if the lifecycle module fails.
object-type	user	(optional) Defines the type of the resource. Allowed values are: <ul style="list-style-type: none"> ■ <code>system-all</code> - A system resource for all server instances and the domain application server. ■ <code>system-admin</code> - A system resource only for the domain application server. ■ <code>system-instance</code> - A system resource for all server instances only. ■ <code>user</code> - A user resource.
enabled	true	(optional) Determines whether the lifecycle module is enabled.

listener-config

Configures the listener class that listens for alerts from notification emitters. For example:

```

<listener-config
    listener-class-name="com.sun.enterprise.admin.notification.MailAlert"
    subscribe-listener-with="LogMBean,ServerStatusMonitor" >
    <property name="recipients" value="Huey@sun.com,Dewey@sun.com" />
    <property name="fromAddress" value="Louie@sun.com" />
    <property name="subject" value="Help!" />
    <property name="includeDiagnostics" value="false" />
    <property name="mailSMTPHost" value="ducks.sun.com" />
</listener-config>
```

Superelements

[“alert-subscription” on page 26](#)

Subelements

The following table describes subelements for the `listener-config` element.

TABLE 1-107 `listener-config` Subelements

Element	Required	Description
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

The following table describes attributes for the `listener-config` element.

TABLE 1-108 `listener-config` Attributes

Attribute	Default	Description
<code>listener-class-name</code>	none	Specifies the class name of the listener. The <code>com.sun.appserv.admin.notification.MailAlert</code> class is provided with the Enterprise Server, but a custom listener can be used.
<code>subscribe-listener-with</code>	none	Specifies a comma-separated list of notification emitters to which the listener listens. The <code>LogMBean</code> and <code>ServerStatusMonitor</code> notification emitters are provided with the Enterprise Server, but custom emitters can be used.

load-balancer

Defines and configures a load balancer. For more information about load balancing in the Enterprise Server, see the [Sun GlassFish Enterprise Server v2.1.1 High Availability Administration Guide](#).

Note – Some topics in the documentation pertain to features that are available only in domains that are configured to support clusters. Examples of domains that support clusters are domains that are created with the cluster profile or the enterprise profile. For information about profiles, see “[Usage Profiles](#)” in *Sun GlassFish Enterprise Server v2.1.1 Administration Guide*.

Superelements

“load-balancers” on page 102

Subelements

The following table describes subelements for the `load-balancer` element.

TABLE 1–109 load-balancer Subelements

Element	Required	Description
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

The following table describes attributes for the `load-balancer` element.

TABLE 1–110 load-balancer Attributes

Attribute	Default	Description
<code>name</code>	none	Specifies the name of the load balancer.
<code>lb-config-name</code>	none	Specifies the name of the “ lb-config ” on page 97 used by the load balancer.
<code>auto-apply-enabled</code>	false	(optional) If true, changes to the specified “ lb-config ” on page 97 are automatically applied to the load balancer.

Properties

The following table describes properties for the `load-balancer` element.

TABLE 1–111 load-balancer Properties

Property	Default	Description
<code>device-host</code>	none	Specifies the host name or IP address for the load balancer.
<code>device-admin-port</code>	none	Specifies the load balancer's administration port number.
<code>ssl-proxy-host</code>	none	Specifies the load balancer's proxy host used for outbound HTTP.

TABLE 1–111 load-balancer Properties (Continued)

Property	Default	Description
ssl-proxy-port	none	Specifies the load balancer's proxy port used for outbound HTTP.

load-balancers

Contains load balancers.

Superelements

[“domain” on page 53](#)

Subelements

The following table describes subelements for the `load-balancers` element.

TABLE 1–112 load-balancers Subelements

Element	Required	Description
“load-balancer” on page 100	zero or more	Defines a load balancer.

log-service

Configures the *server log* file, which stores messages from the default virtual server. Messages from other configured virtual servers also go here, unless the `log-file` attribute is explicitly specified in the `virtual-server` element. The default name is `server.log`.

Other log files are configured by other elements:

- A *virtual server log* file stores messages from a `virtual-server` element that has an explicitly specified `log-file` attribute. See [“virtual-server” on page 146](#).
- The *access log* file stores HTTP access messages from the default virtual server. The default name is `access.log`. See [“access-log” on page 22](#) and [“http-access-log” on page 69](#).
- The *transaction log* files store transaction messages from the default virtual server. The default name of the directory for these files is `tx`. See [“transaction-service” on page 142](#).

Superelements

[“config” on page 40](#), [“node-agent” on page 115](#)

Subelements

The following table describes subelements for the `log-service` element.

TABLE 1-113 log-service Subelements

Element	Required	Description
“module-log-levels” on page 112	zero or one	Specifies log levels.
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

The following table describes attributes for the `log-service` element.

TABLE 1-114 log-service Attributes

Attribute	Default	Description
<code>file</code>	server.log in the directory specified by the <code>log-root</code> attribute of the “domain” on page 53 element	(optional) Overrides the name or location of the server log. The file and directory in which the server log is kept must be writable by the user account under which the server runs. An absolute path overrides the <code>log-root</code> attribute of the “domain” on page 53 element. A relative path is relative to the <code>log-root</code> attribute of the “domain” on page 53 element. If no <code>log-root</code> value is specified, it is relative to <code>domain-dir/config</code> .
<code>use-system-logging</code>	false	(optional) If true, uses the UNIX syslog service to produce and manage logs.
<code>log-handler</code>	none	(optional) Specifies a custom log handler to be added to end of the chain of system handlers to log to a different destination.
<code>log-filter</code>	none	(optional) Specifies a log filter to do custom filtering of log records.
<code>log-to-console</code>	false	(optional) Deprecated and ignored.
<code>log-rotation-limit-in-bytes</code>	2000000	(optional) Log files are rotated when the file size reaches the specified limit.
<code>log-rotation-timelimit-in-minutes</code>	0	(optional) Enables time-based log rotation. The valid range is 60 minutes (1 hour) to 14400 minutes (10*24*60 minutes or 10 days). If the value is zero, the files are rotated based on the size specified in <code>log-rotation-limit-in-bytes</code> . If the value is greater than zero, <code>log-rotation-timelimit-in-minutes</code> takes precedence over <code>log-rotation-limit-in-bytes</code> .
<code>retain-error-statistics-for-hours</code>	5	(optional) Specifies the number of most recent hours for which error statistics are retained in memory. The default and minimum value is 5 hours. The maximum value allowed is 500 hours. Larger values incur additional memory overhead.

Properties

The following table describes properties for the `log-service` element.

TABLE 1-115 log-service Properties

Property	Default	Description
format	time-stamp,product-id, logger-name,thread-info, name-value-pairs, raw-message	Specifies the format of the server log. The comma-separated format tokens can appear in any order and any of them can be omitted.
max-buffered-messages	8192	Specifies the maximum number of log records buffered in memory before being pushed to the server log. This property applies only if asynchronous logging has been enabled by specifying the <code>org.glassfish.logging.async</code> JVM option using the “ jvm-options ” on page 96 element.
push-interval-in-seconds	60	Specifies the interval in seconds at which log messages are written to the server log. This property applies only if asynchronous logging has been enabled by specifying the <code>org.glassfish.logging.async</code> JVM option using the “ jvm-options ” on page 96 element.

M

mail-resource

Defines a JavaMail (`javax.mail.Session`) resource.

Superelements

[“resources” on page 128](#)

Subelements

The following table describes subelements for the `mail-resource` element.

TABLE 1-116 mail-resource Subelements

Element	Required	Description
“description” on page 51	zero or one	Contains a text description of this element.
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

The following table describes attributes for the `mail-resource` element.

TABLE 1-117 mail-resource Attributes

Attribute	Default	Description
jndi-name	none	Specifies the JNDI name for the resource.
store-protocol	imap	(optional) Specifies the storage protocol service, which connects to a mail server, retrieves messages, and saves messages in folder(s). Allowed values are <code>imap</code> , <code>pop3</code> , <code>imaps</code> , and <code>pop3s</code> .
store-protocol-class	<code>com.sun.mail.imap.IMAPStore</code>	(optional) Specifies the service provider implementation class for storage. Allowed values are: <code>com.sun.mail.imap.IMAPStore</code> <code>com.sun.mail.pop3.POP3Store</code> <code>com.sun.mail.imap.IMAPSSLStore</code> <code>com.sun.mail.pop3.POP3SSLStore</code>
transport-protocol	smtp	(optional) Specifies the transport protocol service, which sends messages. Allowed values are <code>smtp</code> and <code>smtpls</code> .
transport-protocol-class	<code>com.sun.mail.smtp.SMTPTransport</code>	(optional) Specifies the service provider implementation class for transport. Allowed values are: <code>com.sun.mail.smtp.SMTPTransport</code> <code>com.sun.mail.smtp.SMTPSSLTransport</code>
host	none	The mail server host name.
user	none	The mail server user name.
from	none	The email address the mail server uses to indicate the message sender.
debug	false	(optional) Determines whether debugging for this resource is enabled.
object-type	user	(optional) Defines the type of the resource. Allowed values are: <ul style="list-style-type: none"> ■ <code>system-all</code> - A system resource for all server instances and the domain application server. ■ <code>system-admin</code> - A system resource only for the domain application server. ■ <code>system-instance</code> - A system resource for all server instances only. ■ <code>user</code> - A user resource.
enabled	true	(optional) Determines whether this resource is enabled at runtime.

Properties

You can set properties for the `mail-resource` element and then get these properties in a JavaMail Session object later. Every property name must start with a `mail-` prefix. The Enterprise Server changes the dash (-) character to a period (.) in the name of the property,

then saves the property to the `MailConfiguration` and `JavaMail Session` objects. If the name of the property doesn't start with `mail-`, the property is ignored.

For example, to define the property `mail.password` in a `JavaMail Session` object, first edit `domain.xml` as follows:

```
...
<mail-resource jndi-name="mail/Session" ...>
    <property name="mail-password" value="adminadmin"/>
</mail-resource>
...
```

After getting the `JavaMail Session` object, get the `mail.password` property to retrieve the value `adminadmin`, as follows:

```
String password = session.getProperty("mail.password");
```

For more information about `JavaMail` properties, see [JavaMail API Documentation \(`http://java.sun.com/products/javamail/javadoc/index.html`\)](http://java.sun.com/products/javamail/javadoc/index.html).

management-rule

Configures a self-management rule, which associates a custom self-tuning, self-configuring, or self-healing action with an event in the Enterprise Server. The action is implemented by an MBean.

Superelements

[“management-rules” on page 107](#)

Subelements

The following table describes subelements for the `management-rule` element.

TABLE 1–118 management-rule Subelements

Element	Required	Description
“description” on page 51	zero or one	<p>Contains a text description of this element.</p> <p>This description is included in server log messages about the management rule. For more information on logging, see “log-service” on page 102 and “module-log-levels” on page 112.</p>
“event” on page 59	only one	Defines the event that triggers the action associated with a management rule.

TABLE 1-118 management-rule Subelements *(Continued)*

Element	Required	Description
“action” on page 23	zero or one	Specifies the action of this management rule. If no action is specified, occurrence of the associated event is logged.

Attributes

The following table describes attributes for the `management-rule` element.

TABLE 1-119 management-rule Attributes

Attribute	Default	Description
<code>name</code>	none	Specifies the name of this management rule.
<code>enabled</code>	true	(optional) If <code>false</code> , disables this management rule.

management-rules

Configures self-management rules, which associate custom self-tuning, self-configuring, and self-healing actions with events in the Enterprise Server.

Superelements

“config” on page 40

Subelements

The following table describes subelements for the `management-rules` element.

TABLE 1-120 management-rules Subelements

Element	Required	Description
“management-rule” on page 106	zero or more	Specifies a management rule.

Attributes

The following table describes attributes for the `management-rules` element.

TABLE 1–121 management-rules Attributes

Attribute	Default	Description
enabled	true	(optional) If false, disables all management rules. If true, the enabled attribute of each rule determines whether it is enabled.

manager-properties

Specifies session manager properties.

Superelements

[“session-manager” on page 135](#)

Subelements

The following table describes subelements for the manager-properties element.

TABLE 1–122 manager-properties Subelements

Element	Required	Description
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

The following table describes attributes for the manager-properties element.

TABLE 1–123 manager-properties Attributes

Attribute	Default	Description
session-file-name	none; state is not preserved across restarts	(optional) Specifies the absolute or relative path to the directory in which the session state is preserved between application restarts, if preserving the state is possible. A relative path is relative to the temporary directory for this web application. Applicable to the web container only if the persistence-type attribute of the “web-container-availability” on page 152 element is memory.
reap-interval-in-seconds	60	(optional) Specifies the time between checks for expired sessions. If the persistence-frequency attribute of the web-container-availability element is set to time-based, active sessions are stored at this interval. Set this value lower than the frequency at which session data changes. For example, this value should be as low as possible (1 second) for a hit counter servlet on a frequently accessed web site, or you could lose the last few hits each time you restart the server.

TABLE 1-123 manager-properties Attributes *(Continued)*

Attribute	Default	Description
max-sessions	-1	(optional) Specifies the maximum number of sessions that can be in cache, or -1 for no limit. After this, an attempt to create a new session causes an <code>IllegalStateException</code> to be thrown.
session-id-generator-classname	internal class generator	(optional) Not implemented. Use the <code>uuid-impl-class</code> property of the “web-container-availability” on page 152 element instead.

mbean

Specifies an MBean, which implements the `javax.management.NotificationListener` interface.

Superelements

[“applications” on page 28](#)

Subelements

The following table describes subelements for the `mbean` element.

TABLE 1-124 mbean Subelements

Element	Required	Description
“description” on page 51	zero or one	Contains a text description of this element.
“property” on page 121	zero or more	Specifies a property. Property subelements of the <code>mbean</code> element store the names and values of attributes defined in the MBean implementation class.

Attributes

The following table describes attributes for the `mbean` element.

TABLE 1-125 mbean Attributes

Attribute	Default	Description
name	value of <code>impl-class-name</code>	The name of the MBean. The name must represent a value of a property in the <code>property-list</code> of an MBean <code>ObjectName</code> . The name is a primary key for the MBean. This is read-only.

TABLE 1–125 mbean Attributes *(Continued)*

Attribute	Default	Description
object-type	user	(optional) Defines the type of the resource. This is read-only. Allowed values are: <ul style="list-style-type: none"> ■ system-all - A system resource for all server instances and the domain application server. ■ system-admin - A system resource only for the domain application server. ■ system-instance - A system resource for all server instances only. ■ user - A user resource.
impl-class-name	none	Defines the fully qualified class name of the MBean implementation. This is read-only.
object-name	none	Defines a system-generated object name for this MBean. This is read-only.
enabled	true	(optional) Determines whether the MBean is enabled. If false, the MBean is not registered in the runtime environment even if the reference is enabled.

mdb-container

Configures the message-driven bean (MDB) container.

Superelements

[“config” on page 40](#)

Subelements

The following table describes subelements for the `mdb-container` element.

TABLE 1–126 `mdb-container` Subelements

Element	Required	Description
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

The following table describes attributes for the `mdb-container` element.

TABLE 1–127 `mdb-container` Attributes

Attribute	Default	Description
steady-pool-size	10	(optional) Specifies the initial and minimum number of beans maintained in the pool.

TABLE 1-127 `mdb-container` Attributes *(Continued)*

Attribute	Default	Description
pool-resize-quantity	2	(optional) Specifies the number of beans to be removed when the <code>idle-timeout-in-seconds</code> timer expires. A cleaner thread removes any unused instances. Must be <code>0</code> or greater and less than <code>max-pool-size</code> . The pool is not resized below the <code>steady-pool-size</code> .
<code>max-pool-size</code>	60	(optional) Specifies the maximum number of beans that can be created to satisfy client requests.
<code>idle-timeout-in-seconds</code>	600	(optional) Specifies the maximum time that a bean can remain idle in the pool. After this amount of time, the bean is destroyed. A value of <code>0</code> means a bean can remain idle indefinitely.

Properties

The following table describes properties for the `mdb-container` element.

TABLE 1-128 `mdb-container` Properties

Property	Default	Description
<code>cmt-max-runtime-exceptions</code>	1	Specifies the maximum number of <code>RuntimeException</code> occurrences allowed from a message-driven bean's <code>onMessage()</code> method when container-managed transactions are used. Deprecated.

message-security-config

Specifies configurations for message security providers.

Superelements

[“security-service” on page 131](#)

Subelements

The following table describes subelements for the `message-security-config` element.

TABLE 1-129 `message-security-config` Subelements

Element	Required	Description
“provider-config” on page 123	one or more	Specifies a configuration for one message security provider.

Attributes

The following table describes attributes for the `message-security-config` element.

TABLE 1–130 message-security-config Attributes

Attribute	Default	Description
auth-layer	SOAP	Specifies the message layer at which authentication is performed. The value must be SOAP or HttpServlet.
default-provider	none	(optional) Specifies the server provider that is invoked for any application not bound to a specific server provider.
default-client-provider	none	(optional) Specifies the client provider that is invoked for any application not bound to a specific client provider.

module-log-levels

Controls the level of messages logged by server subsystems to the server log. Allowed values (levels) of each subsystem attribute are, from highest to lowest: FINEST, FINER, FINE, CONFIG, INFO, WARNING, SEVERE, and OFF. Each value logs all messages for all lower values. The default value is INFO, which logs all INFO, SEVERE, and WARNING messages.

Superelements

[“log-service” on page 102](#)

Subelements

The following table describes subelements for the `module-log-levels` element.

TABLE 1–131 module-log-levels Subelements

Element	Required	Description
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

The following table describes attributes for the `module-log-levels` element. The attribute names are the names of the Enterprise Server system loggers.

TABLE 1–132 module-log-levels Attributes

Attribute	Default	Description
root	INFO	(optional) Specifies the default level of messages logged by the entire Enterprise Server installation.
server	INFO	(optional) Specifies the default level of messages logged by the server instance.

TABLE 1-132 module-log-levels Attributes *(Continued)*

Attribute	Default	Description
ejb-container	INFO	(optional) Specifies the level of messages logged by the EJB container.
cmp-container	INFO	(optional) Specifies the level of messages logged by the CMP subsystem of the EJB container.
mdb-container	INFO	(optional) Specifies the level of messages logged by the MDB container.
web-container	INFO	(optional) Specifies the level of messages logged by the web container.
classloader	INFO	(optional) Specifies the level of messages logged by the classloader hierarchy.
configuration	INFO	(optional) Specifies the level of messages logged by the configuration subsystem.
naming	INFO	(optional) Specifies the level of messages logged by the naming subsystem.
security	INFO	(optional) Specifies the level of messages logged by the security subsystem.
jts	INFO	(optional) Specifies the level of messages logged by the Java Transaction Service.
jta	INFO	(optional) Specifies the level of messages logged by the Java Transaction API.
admin	INFO	(optional) Specifies the level of messages logged by the Administration Console subsystem.
deployment	INFO	(optional) Specifies the level of messages logged by the deployment subsystem.
verifier	INFO	(optional) Specifies the level of messages logged by the deployment descriptor verifier.
jaxr	INFO	(optional) Specifies the level of messages logged by the XML registry.
jaxrpc	INFO	(optional) Specifies the level of messages logged by the XML RPC module.
saaj	INFO	(optional) Specifies the level of messages logged by the SOAP with Attachments API for Java module.
corba	INFO	(optional) Specifies the level of messages logged by the ORB.
javamail	INFO	(optional) Specifies the level of messages logged by the JavaMail subsystem.
jms	INFO	(optional) Specifies the level of messages logged by the Java Message Service.
connector	INFO	(optional) Specifies the level of messages logged by the connector subsystem.
jdo	INFO	(optional) Specifies the level of messages logged by the Java Data Objects module.
cmp	INFO	(optional) Specifies the level of messages logged by the CMP subsystem.
util	INFO	(optional) Specifies the level of messages logged by the utility subsystem.
resource-adapter	INFO	(optional) Specifies the level of messages logged by the resource adapter subsystem.
synchronization	INFO	(optional) Specifies the level of messages logged by the synchronization subsystem.
node-agent	INFO	(optional) Specifies the level of messages logged by the node agent subsystem.
self-management	INFO	(optional) Specifies the level of messages logged by the self-management (management rules) subsystem.

TABLE 1–132 module-log-levels Attributes *(Continued)*

Attribute	Default	Description
group-management-service	INFO	(optional) Specifies the level of messages logged by the Group Management Service.
management-event	INFO	(optional) Specifies the level of messages logged by the self-management event subsystem.

module-monitoring-levels

Controls the level of monitoring of server subsystems. Allowed values of each subsystem attribute are LOW, HIGH, and OFF.

Superelements

[“monitoring-service” on page 115](#)

Subelements

The following table describes subelements for the module-monitoring-levels element.

TABLE 1–133 module-monitoring-levels Subelements

Element	Required	Description
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

TABLE 1–134 module-monitoring-levels Attributes

Attribute	Default	Description
thread-pool	OFF	(optional) Specifies the level of monitoring of the thread pool subsystem.
orb	OFF	(optional) Specifies the level of monitoring of the ORB.
ejb-container	OFF	(optional) Specifies the level of monitoring of the EJB container.
web-container	OFF	(optional) Specifies the level of monitoring of the web container.
transaction-service	OFF	(optional) Specifies the level of monitoring of the transaction service.
http-service	OFF	(optional) Specifies the level of monitoring of the HTTP service.
jdbc-connection-pool	OFF	(optional) Specifies the level of monitoring of the JDBC connection pool subsystem.
connector-connection-pool	OFF	(optional) Specifies the level of monitoring of the connector connection pool subsystem.

TABLE 1-134 module-monitoring-levels Attributes *(Continued)*

Attribute	Default	Description
connector-service	OFF	(optional) Specifies the level of monitoring of the connector service.
jms-service	OFF	(optional) Specifies the level of monitoring of the JMS service.
jvm	OFF	(optional) Specifies the level of monitoring of the JVM.

monitoring-service

Configures the monitoring service.

Superelements

[“config” on page 40](#)

Subelements

The following table describes subelements for the `monitoring-service` element.

TABLE 1-135 monitoring-service Subelements

Element	Required	Description
“module-monitoring-levels” on page 114	zero or one	Controls the level of monitoring of server subsystems.
“property” on page 121	zero or more	Specifies a property or a variable.

N

node-agent

Defines a node agent, which manages server instances on a host machine.

Superelements

[“node-agents” on page 116](#)

Subelements

The following table describes subelements for the `node-agent` element.

TABLE 1–136 node-agent Subelements

Element	Required	Description
“jmx-connector” on page 94	zero or one	Configures a JSR 160/255 compliant remote JMX connector.
“auth-realm” on page 29	zero or one	Defines a realm for authentication.
“log-service” on page 102	only one	Configures the system logging service.
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

The following table describes attributes for the node-agent element.

TABLE 1–137 node-agent Attributes

Attribute	Default	Description
name	none	Specifies the node agent name.
system-jmx-connector-name	none	Specifies the name of the internal “jmx-connector” on page 94.
start-servers-in-startup	true	(optional) If true, starts all managed server instances when the node agent is started.

Properties

The following table describes properties for the node-agent element.

TABLE 1–138 node-agent Properties

Property	Default	Description
INSTANCE-SYNC-JVM-OPTIONS	default Enterprise Server JVM options	Sets options for the server instance synchronization JVM. Setting options that limit memory usage helps prevent OutOfMemory errors when large applications are synchronized or when memory is constrained. For more information, see the Sun GlassFish Enterprise Server v2.1.1 Administration Guide .

node-agents

Contains node agents.

Superelements

“domain” on page 53

Subelements

The following table describes subelements for the node-agents element.

TABLE 1–139 node-agents Subelements

Element	Required	Description
“node-agent” on page 115	zero or more	Defines a node agent, which manages server instances on a host machine.

0

orb

Configures the ORB.

To enable SSL for outbound connections, include an “ssl-client-config” on page 138 subelement in the parent `iiop-service` element.

Superelements

“iiop-service” on page 80

Subelements

The following table describes subelements for the `orb` element.

TABLE 1–140 orb Subelements

Element	Required	Description
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

The following table describes attributes for the `orb` element.

TABLE 1–141 orb Attributes

Attribute	Default	Description
<code>use-thread-pool-ids</code>	none	Specifies a comma-separated list of <code>thread-pool-id</code> values defined in “ thread-pool ” on page 141 elements used by the ORB.
<code>message-fragment-size</code>	1024	(optional) GIOPv1.2 messages larger than this number of bytes are fragmented.
<code>max-connections</code>	1024	(optional) The maximum number of incoming connections on all IIOP listeners. Legal values are integers.

overload-protection-service

Configures the overload protection service for HTTP requests.

Superelements

[“config” on page 40](#)

Subelements

none

Attributes

The following table describes attributes for the `overload-protection-service` element.

TABLE 1-142 `overload-protection-service` Attributes

Attribute	Default	Description
<code>enabled</code>	<code>false</code>	If <code>true</code> , the overload protection manager is enabled and operates according to <code>cpu-overload-protection</code> , <code>memory-overload-protection</code> , and other <code>overload-protection-service</code> attributes. Overload regulation protects the HTTP container from too high CPU or memory usage.
<code>cpu-overload-protection</code>	<code>false</code>	If <code>true</code> , CPU overload protection is enabled. Applicable only if <code>enabled</code> is set to <code>true</code> .
<code>memory-overload-protection</code>	<code>false</code>	If <code>true</code> , memory overload protection is enabled. Applicable only if <code>enabled</code> is set to <code>true</code> .
<code>cpu-http-threshold</code>	70	Specifies the CPU usage threshold level for HTTP requests. Allowed values are <code>0</code> to <code>100</code> . Any SIP requests received when the system is operating beyond this threshold are responded to with a <code>503</code> error. Applicable only if <code>cpu-overload-protection</code> is set to <code>true</code> .
<code>mem-http-threshold</code>	85	Specifies the memory usage threshold level for HTTP requests. Allowed values are <code>0</code> to <code>100</code> . Any SIP requests received when the system is operating beyond this threshold are responded to with a <code>503</code> error. Applicable only if <code>memory-overload-protection</code> is set to <code>true</code> .
<code>cpu-mm-threshold</code>	99	Specifies the CPU usage threshold level when all messages are dropped. Allowed values are <code>0</code> to <code>100</code> . Applicable only if <code>cpu-overload-protection</code> is set to <code>true</code> .
<code>mem-mm-threshold</code>	99	Specifies the memory usage threshold level when all messages are dropped. Allowed values are <code>0</code> to <code>100</code> . Applicable only if <code>memory-overload-protection</code> is set to <code>true</code> .
<code>sample-rate</code>	2	Specifies the sample rate in seconds for updating threshold levels. Allowed values are <code>1</code> to <code>120</code> seconds.

TABLE 1-142 overload-protection-service Attributes *(Continued)*

Attribute	Default	Description
number-of-samples	5	Specifies the number of consecutive samples needed before a threshold is raised. Allowed values are 2 to 20.
retry-after-interval	10	Specifies the interval in seconds between response retries. This is part of the <code>retry-after</code> header in a 503 response.
cpu-overload-activation-algorithm	MEDIAN	Specifies the activation algorithm for CPU overload protection. Allowed values are MEDIAN and CONSECUTIVE.
cpu-overload-deactivation-algorithm	CONSECUTIVE	Specifies the deactivation algorithm for CPU overload protection. Allowed values are MEDIAN and CONSECUTIVE.
mem-overload-activation-algorithm	MEDIAN	Specifies the activation algorithm for memory overload protection. Allowed values are MEDIAN and CONSECUTIVE.
mem-overload-deactivation-algorithm	CONSECUTIVE	Specifies the deactivation algorithm for memory overload protection. Allowed values are MEDIAN and CONSECUTIVE.
mm-threshold-http-wait-time	2	Specifies the time in seconds for which a thread is held before being released back to the thread pool. Used in the context of maximum overload for HTTP requests.

P

persistence-manager-factory-resource

Defines a persistence manager factory resource for container-managed persistence (CMP). Deprecated, and included for backward compatibility only. Use a “[jdbc-resource](#)” on page 89 element instead.

Superelements

[“resources” on page 128](#)

Subelements

The following table describes subelements for the `persistence-manager-factory-resource` element.

TABLE 1-143 `persistence-manager-factory-resource` Subelements

Element	Required	Description
“description” on page 51	zero or one	Contains a text description of this element.

TABLE 1–143 persistence-manager-factory-resource Subelements *(Continued)*

Element	Required	Description
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

The following table describes attributes for the persistence-manager-factory-resource element.

TABLE 1–144 persistence-manager-factory-resource Attributes

Attribute	Default	Description
jndi-name	none	Specifies the JNDI name for the resource.
factory-class	com.sun.jdo.spi.persistence.support.sqlstore.impl.PersistenceManagerFactoryImpl	(optional) Deprecated. Do not specify this attribute for the built-in CMP implementation.
jdbc-resource-jndi-name	none	Specifies the “jdbc-resource” on page 89 from which database connections are obtained. Must be the jndi-name of an existing jdbc-resource.
object-type	user	(optional) Defines the type of the resource. Allowed values are: <ul style="list-style-type: none"> ■ system-all - A system resource for all server instances and the domain application server. ■ system-admin - A system resource only for the domain application server. ■ system-instance - A system resource for all server instances only. ■ user - A user resource.
enabled	true	(optional) Determines whether this resource is enabled at runtime.

principal

Contains the principal of the servlet or EJB client.

Superelements

“security-map” on page 130

Subelements

none - contains data

profiler

Configures a profiler for use with the Enterprise Server. For more information about profilers, see the [Sun GlassFish Enterprise Server v2.1.1 Developer's Guide](#).

Superelements

[“java-config” on page 83](#)

Subelements

The following table describes subelements for the `profiler` element.

TABLE 1–145 `profiler` Subelements

Element	Required	Description
“jvm-options” on page 96	zero or more	Contains profiler-specific JVM command line options.
“property” on page 121	zero or more	Specifies a property or a variable.

Note – Subelements of a `profiler` element can occur in any order.

Attributes

The following table describes attributes for the `profiler` element.

TABLE 1–146 `profiler` Attributes

Attribute	Default	Description
<code>name</code>	none	Specifies the name of the profiler.
<code>classpath</code>	none	(optional) Specifies the classpath for the profiler.
<code>native-library-path</code>	none	(optional) Specifies the native library path for the profiler.
<code>enabled</code>	true	(optional) Determines whether the profiler is enabled.

property

Specifies a property. A property adds configuration information to its parent element that is one or both of the following:

- Optional with respect to the Enterprise Server
- Needed by a system or object that the Enterprise Server doesn't have knowledge of, such as an LDAP server or a Java class

For example, an `auth-realm` element can include property subelements:

```
<auth-realm name="file"
    classname="com.sun.enterprise.security.auth.realm.file.FileRealm">
    <property name="file" value="domain-dir/config/keyfile"/>
    <property name="jaas-context" value="fileRealm"/>
</auth-realm>
```

Which properties an `auth-realm` element uses depends on the value of the `auth-realm` element's `name` attribute. The `file` realm uses `file` and `jaas-context` properties. Other realms use different properties.

Superelements

[“admin-object-resource” on page 23](#), [“admin-service” on page 24](#), [“alert-service” on page 25](#), [“appclient-module” on page 26](#), [“audit-module” on page 29](#), [“auth-realm” on page 29](#), [“availability-service” on page 32](#), [“cluster” on page 36](#), [“config” on page 40](#), [“connector-connection-pool” on page 42](#), [“connector-module” on page 46](#), [“connector-resource” on page 47](#), [“custom-resource” on page 49](#), [“das-config” on page 50](#), [“diagnostic-service” on page 52](#), [“domain” on page 53](#), [“ejb-container” on page 54](#), [“ejb-container-availability” on page 56](#), [“ejb-module” on page 57](#), [“ejb-timer-service” on page 59](#), [“event” on page 59](#), [“extension-module” on page 64](#), [“external-jndi-resource” on page 65](#), [“filter-config” on page 66](#), [“group-management-service” on page 67](#), [“http-listener” on page 71](#), [“http-service” on page 76](#), [“iiop-listener” on page 79](#), [“j2ee-application” on page 81](#), [“jacc-provider” on page 82](#), [“java-config” on page 83](#), [“jdbc-connection-pool” on page 85](#), [“jdbc-resource” on page 89](#), [“jms-availability” on page 90](#), [“jms-host” on page 91](#), [“jms-service” on page 92](#), [“jmx-connector” on page 94](#), [“lb-config” on page 97](#), [“lifecycle-module” on page 98](#), [“listener-config” on page 99](#), [“load-balancer” on page 100](#), [“log-service” on page 102](#), [“mail-resource” on page 104](#), [“management-rule” on page 106](#), [“manager-properties” on page 108](#), [“mbean” on page 109](#), [“mdb-container” on page 110](#), [“module-log-levels” on page 112](#), [“module-monitoring-levels” on page 114](#), [“monitoring-service” on page 115](#), [“node-agent” on page 115](#), [“orb” on page 117](#), [“persistence-manager-factory-resource” on page 119](#), [“profiler” on page 121](#), [“provider-config” on page 123](#), [“resource-adapter-config” on page 126](#), [“security-service” on page 131](#), [“server” on page 132](#), [“session-properties” on page 136](#), [“store-properties” on page 139](#), [“transaction-service” on page 142](#), [“virtual-server” on page 146](#), [“web-container” on page 151](#), [“web-container-availability” on page 152](#), [“web-module” on page 155](#)

Subelements

The following table describes subelements for the `property` element.

TABLE 1–147 property Subelements

Element	Required	Description
“description” on page 51	zero or one	Contains a text description of this element.

Attributes

The following table describes attributes for the `property` element.

TABLE 1–148 property Attributes

Attribute	Default	Description
<code>name</code>	none	Specifies the name of the property or variable.
<code>value</code>	none	Specifies the value of the property or variable.

provider-config

Specifies a configuration for one message security provider.

Although the `request-policy` and `response-policy` subelements are optional, the `provider-config` element does nothing if they are not specified.

Use property subelements to configure provider-specific properties. Property values are passed to the provider when its `initialize` method is called.

Superelements

“message-security-config” on page 111

Subelements

The following table describes subelements for the `provider-config` element.

TABLE 1–149 provider-config Subelements

Element	Required	Description
“request-policy” on page 125	zero or one	Defines the authentication policy requirements of the authentication provider’s request processing.
“response-policy” on page 129	zero or one	Defines the authentication policy requirements of the authentication provider’s response processing.
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

The following table describes attributes for the provider-config element.

TABLE 1–150 provider-config Attributes

Attribute	Default	Description
provider-id	none	Specifies a unique identifier for this provider-config element.
provider-type	none	Specifies whether the provider is a client, server, or client-server authentication provider.
class-name	none	Specifies the Java implementation class of the provider. Client authentication providers must implement the com.sun.enterprise.security.jauth.ClientAuthModule interface. Server authentication providers must implement the com.sun.enterprise.security.jauth.ServerAuthModule interface. Client-server providers must implement both interfaces.

Properties

The following table describes properties for the provider-config element.

TABLE 1–151 provider-config Properties

Property	Default	Description
security.config	<i>domain-dir/config/wss-server-config-1.0.xml</i>	Specifies the location of the message security configuration file. To point to a configuration file in the <i>domain-dir/config</i> directory, use the prefix \${com.sun.aas.instanceRoot}/config/, for example: \${com.sun.aas.instanceRoot}/config/wss-server-config-1.0.xml
debug	false	If true, enables dumping of server provider debug messages to the server log.
dynamic.username.password	false	If true, signals the provider runtime to collect the user name and password from the CallbackHandler for each request. If false, the user name and password for wsse:UsernameToken(s) is collected once, during module initialization. This property is only applicable for a ClientAuthModule.
encryption.key.alias	s1as	Specifies the encryption key used by the provider. The key is identified by its keystore alias.
signature.key.alias	s1as	Specifies the signature key used by the provider. The key is identified by its keystore alias.

R

registry-location

Specifies the registry where web service endpoint artifacts are published.

Superelements

[“web-service-endpoint” on page 157](#)

Subelements

none

Attributes

The following table describes attributes for the `registry-location` element.

TABLE 1-152 `registry-location` Attributes

Attribute	Default	Description
<code>connector-resource-jndi-name</code>	none	Specifies the <code>jndi-name</code> of the “connector-resource” on page 47 used as the registry.

request-policy

Defines the authentication policy requirements of the authentication provider’s request processing.

Superelements

[“provider-config” on page 123](#)

Subelements

none

Attributes

The following table describes attributes for the `request-policy` element.

TABLE 1–153 request-policy Attributes

Attribute	Default	Description
auth-source	none	Specifies the type of required authentication, either <code>sender</code> (user name and password) or <code>content</code> (digital signature).
auth-recipient	none	Specifies whether recipient authentication occurs before or after content authentication. Allowed values are <code>before-content</code> and <code>after-content</code> .

request-processing

Configures request processing threads.

Superelements

[“http-service” on page 76](#)

Subelements

none

Attributes

The following table describes attributes for the `request-processing` element.

TABLE 1–154 request-processing Attributes

Attribute	Default	Description
thread-count	5	(optional) Specifies the maximum number of request processing threads.
initial-thread-count	2	(optional) Specifies the number of request processing threads that are available when the server starts up.
thread-increment	1	(optional) Specifies the number of request processing threads added when the number of requests exceeds the <code>initial-thread-count</code> . Set this attribute to a value greater than 1 if <code>thread-count</code> is greater than 10.
request-timeout-in-seconds	60	(optional) Specifies the time at which the request times out.
header-buffer-length-in-bytes	8192	(optional) Specifies the size of the buffer used by the request processing threads to read the request data.

resource-adapter-config

Defines a connector (resource adapter) configuration. Stores configuration information for the resource adapter JavaBean in property subelements.

Superelements

[“resources” on page 128](#)

Subelements

The following table describes subelements for the `resource-adapter-config` element.

TABLE 1-155 `resource-adapter-config` Subelements

Element	Required	Description
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

The following table describes attributes for the `resource-adapter-config` element.

TABLE 1-156 `resource-adapter-config` Attributes

Attribute	Default	Description
<code>name</code>	none	(optional) Not used. See <code>resource-adapter-name</code> .
<code>thread-pool-ids</code>	none	(optional) Specifies the id of a “ thread-pool on page 141” element.
<code>object-type</code>	user	(optional) Defines the type of the resource. Allowed values are: <ul style="list-style-type: none"> ■ <code>system-all</code> - A system resource for all server instances and the domain application server. ■ <code>system-admin</code> - A system resource only for the domain application server. ■ <code>system-instance</code> - A system resource for all server instances only. ■ <code>user</code> - A user resource.
<code>resource-adapter-name</code>	none	Specifies the <code>name</code> attribute of a deployed “ connector-module on page 46”. If the resource adapter is embedded in an application, then it is <code>app_name#rar_name</code> .

Properties

Properties of the `resource-adapter-config` element are the names of setter methods of the `resourceadapter-class` element in the `ra.xml` file, which defines the class name of the resource adapter JavaBean. Any properties defined here override the default values present in `ra.xml`.

resource-ref

References a resource deployed to the server instance or cluster.

Note – Some topics in the documentation pertain to features that are available only in domains that are configured to support clusters. Examples of domains that support clusters are domains that are created with the cluster profile or the enterprise profile. For information about profiles, see “[Usage Profiles](#)” in *Sun GlassFish Enterprise Server v2.1.1 Administration Guide*.

Superelements

“cluster” on page 36, “server” on page 132

Subelements

none

Attributes

The following table describes attributes for the `resource-ref` element.

TABLE 1–157 `resource-ref` Attributes

Attribute	Default	Description
<code>enabled</code>	<code>true</code>	(optional) Determines whether the resource is enabled.
<code>ref</code>	<code>none</code>	References the <code>name</code> attribute of a “ custom-resource ” on page 49, “ external-jndi-resource ” on page 65, “ jdbc-resource ” on page 89, “ mail-resource ” on page 104, “ persistence-manager-factory-resource ” on page 119, “ admin-object-resource ” on page 23 “ resource-adapter-config ” on page 126, “ jdbc-connection-pool ” on page 85, or “ connector-connection-pool ” on page 42 element.

resources

Contains configured resources, such as database connections, JavaMail™ sessions, and so on.

Note – You must specify a Java Naming and Directory Interface™ (JNDI) name for each resource. To avoid collisions with names of other enterprise resources in JNDI, and to avoid portability problems, all names in an Enterprise Server application should begin with the string `java:comp/env`.

Superelements

“[domain](#)” on page 53

Subelements

The following table describes subelements for the `resources` element.

TABLE 1–158 resources Subelements

Element	Required	Description
“custom-resource” on page 49	zero or more	Defines a custom resource.
“external-jndi-resource” on page 65	zero or more	Defines a resource that resides in an external JNDI repository.
“jdbc-resource” on page 89	zero or more	Defines a JDBC (Java Database Connectivity) resource.
“mail-resource” on page 104	zero or more	Defines a JavaMail resource.
“persistence-manager-factory-resource” on page 119	zero or more	Defines a persistence manager factory resource for CMP. Deprecated. Use a “jdbc-resource” on page 89 element instead.
“admin-object-resource” on page 23	zero or more	Defines an administered object for an inbound resource adapter.
“connector-resource” on page 47	zero or more	Defines a connector (resource adapter) resource.
“resource-adapter-config” on page 126	zero or more	Defines a resource adapter configuration.
“jdbc-connection-pool” on page 85	zero or more	Defines the properties that are required for creating a JDBC connection pool.
“connector-connection-pool” on page 42	zero or more	Defines the properties that are required for creating a connector connection pool.

Note – Subelements of a resources element can occur in any order.

response-policy

Defines the authentication policy requirements of the authentication provider’s response processing.

Superelements

“provider-config” on page 123

Subelements

none

Attributes

The following table describes attributes for the response-policy element.

TABLE 1–159 response-policy Attributes

Attribute	Default	Description
auth-source	none	Specifies the type of required authentication, either <code>sender</code> (user name and password) or <code>content</code> (digital signature).
auth-recipient	none	Specifies whether recipient authentication occurs before or after content authentication. Allowed values are <code>before-content</code> and <code>after-content</code> .

S

security-map

Maps the principal received during servlet or EJB authentication to the credentials accepted by the EIS.

Superelements

[“connector-connection-pool” on page 42](#)

Subelements

The following table describes subelements for the `security-map` element.

TABLE 1–160 security-map Subelements

Element	Required	Description
“principal” on page 120	one or more	Contains the principal of the servlet or EJB client.
“user-group” on page 146	one or more	Contains the group to which the principal belongs.
“backend-principal” on page 35	only one	Specifies the user name and password required by the EIS.

Attributes

The following table describes attributes for the `security-map` element.

TABLE 1–161 security-map Attributes

Attribute	Default	Description
<code>name</code>	none	Specifies a name for the security mapping.

security-service

Defines parameters and configuration information needed by the Java EE security service. For SSL configuration, see “ssl” on page 137. For connector module security, see “security-map” on page 130.

Superelements

[“config” on page 40](#)

Subelements

The following table describes subelements for the `security-service` element.

TABLE 1–162 `security-service` Subelements

Element	Required	Description
“auth-realm” on page 29	one or more	Defines a realm for authentication.
“jacc-provider” on page 82	one or more	Specifies a Java Authorization Contract for Containers (JACC) provider for pluggable authorization.
“audit-module” on page 29	zero or more	Specifies an optional plug-in module that implements audit capabilities.
“message-security-config” on page 111	zero or more	Specifies configurations for message security providers.
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

The following table describes attributes for the `security-service` element.

TABLE 1–163 `security-service` Attributes

Attribute	Default	Description
<code>default-realm</code>	<code>file</code>	(optional) Specifies the active authentication realm (an <code>auth-realm</code> name attribute) for this server instance.
<code>default-principal</code>	<code>none</code>	(optional) Used as the identity of the default security context when necessary and when no principal is provided. This attribute need not be set for normal server operation.
<code>default-principal-password</code>	<code>none</code>	(optional) The password of the default principal. This attribute need not be set for normal server operation.
<code>anonymous-role</code>	<code>attribute is deprecated</code>	(optional) Deprecated. Do not use.

TABLE 1-163 security-service Attributes *(Continued)*

Attribute	Default	Description
audit-enabled	false	(optional) If true, additional access logging is performed to provide audit information. Audit information consists of: <ul style="list-style-type: none">■ Authentication success and failure events■ Servlet and EJB access grants and denials
jacc	default	(optional) Specifies the name of the “jacc-provider” on page 82 element to use for setting up the JACC infrastructure. Do not change the default value unless you are adding a custom JACC provider.
audit-modules	default	(optional) Specifies a space-separated list of audit provider modules used by the audit subsystem. The default value refers to the internal log-based audit module.
activate-default-principal-to-role-mapping	false	(optional) Applies a default principal for role mapping to any application that does not have an application-specific mapping defined. Every role is mapped to an instance of a <code>java.security.Principal</code> implementation class defined by <code>mapped-principal-class</code> . This class has the same name as the role.
mapped-principal-class	<code>com.sun.enterprise.deployment.Group</code>	(optional) Customizes the <code>java.security.Principal</code> implementation class used when <code>activate-default-principal-to-role-mapping</code> is set to true.

server

Defines a server instance, which is a Java EE compliant container. One server instance is specially designated as a domain administration server (DAS). The “admin-service” on page 24 subelement of the “config” on page 40 element referenced by a server’s config-ref attribute determines whether the server is the DAS.

Note – Server instances are not the same thing as virtual servers. Each server instance is a completely separate server that contains one or more virtual servers.

Superelements

“servers” on page 134

Subelements

The following table describes subelements for the server element.

TABLE 1–164 server Subelements

Element	Required	Description
“application-ref” on page 27	zero or more	References an application or module deployed to the server instance.
“resource-ref” on page 127	zero or more	References a resource deployed to the server instance.
“system-property” on page 139	zero or more	Specifies a system property.
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

The following table describes attributes for the `server` element.

TABLE 1–165 server Attributes

Attribute	Default	Description
<code>name</code>	none	Specifies the name of the server instance.
<code>config-ref</code>	default “config” on page 40 element’s name, <code>server-config</code>	(optional) References the name of the “config” on page 40 used by the server instance.
<code>node-agent-ref</code>	node agent created when the server instance was created	(optional) References the name of the “node-agent” on page 115 used by the server instance.
<code>lb-weight</code>	100	(optional) Specifies a server instance’s relative weight for load balancing. Each server instance in a cluster has a weight, which represents the relative processing capacity of that instance. Weighted load balancing policies use this weight for load balancing requests within the cluster. It is the responsibility of the administrator to set the relative weights correctly, keeping in mind deployed hardware capacity.

server-ref

References a server instance.

Note – Some topics in the documentation pertain to features that are available only in domains that are configured to support clusters. Examples of domains that support clusters are domains that are created with the cluster profile or the enterprise profile. For information about profiles, see “Usage Profiles” in *Sun GlassFish Enterprise Server v2.1.1 Administration Guide*.

Superelements

“cluster” on page 36, “lb-config” on page 97

Subelements

The following table describes subelements for the `server-ref` element.

TABLE 1-166 `server-ref` Subelements

Element	Required	Description
“health-checker” on page 68	zero or one	Defines a health checker for the referenced server instance.

Attributes

The following table describes attributes for the `server-ref` element.

TABLE 1-167 `server-ref` Attributes

Attribute	Default	Description
<code>ref</code>	<code>none</code>	References the name attribute of a “ server ” on page 132 element.
<code>disable-timeout-in-minutes</code>	<code>30</code>	(optional) Specifies the time it takes this server instance to reach a quiescent state after having been disabled.
<code>lb-enabled</code>	<code>false</code>	(optional) If <code>true</code> , all load-balancers that reference this server instance consider it available to them.
<code>enabled</code>	<code>true</code>	(optional) Determines whether the server instance is enabled.

servers

Contains server instances.

Superelements

[“domain” on page 53](#)

Subelements

The following table describes subelements for the `servers` element.

TABLE 1-168 `servers` Subelements

Element	Required	Description
“server” on page 132	only one (developer profile) zero or more (cluster and enterprise profiles)	Defines a server instance.

session-config

Specifies session configuration information for the entire web container. Individual web applications can override these settings using the corresponding elements in their `sun-web.xml` files.

Superelements

[“web-container” on page 151](#)

Subelements

The following table describes subelements for the `session-config` element.

TABLE 1-169 session-config Subelements

Element	Required	Description
“session-manager” on page 135	zero or one	Specifies session manager configuration information.
“session-properties” on page 136	zero or one	Specifies session properties.

session-manager

Specifies session manager information.

Note – The session manager interface is unstable. An unstable interface might be experimental or transitional, and hence might change incompatibly, be removed, or be replaced by a more stable interface in the next release.

Superelements

[“session-config” on page 135](#)

Subelements

The following table describes subelements for the `session-manager` element.

TABLE 1-170 session-manager Subelements

Element	Required	Description
“manager-properties” on page 108	zero or one	Specifies session manager properties.

TABLE 1-170 session-manager Subelements (*Continued*)

Element	Required	Description
“store-properties” on page 139	zero or one	Specifies session persistence (storage) properties.

session-properties

Specifies session properties.

Superelements

“session-config” on page 135

Subelements

The following table describes subelements for the session-properties element.

TABLE 1-171 session-properties Subelements

Element	Required	Description
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

TABLE 1-172 session-properties Attributes

Attribute	Default	Description
timeout-in-seconds	600	(optional) Specifies the default maximum inactive interval (in seconds) for all sessions created in this web module. If set to 0 or less, sessions in this web module never expire. If a session-timeout element is specified in the web.xml file, the session-timeout value overrides any timeout-in-seconds value. If neither session-timeout nor timeout-in-seconds is specified, the timeout-in-seconds default is used. Note that the session-timeout element in web.xml is specified in minutes, not seconds.

Properties

The following table describes properties for the session-properties element.

TABLE 1–173 session-properties Properties

Property	Default	Description
enableCookies	true	Uses cookies for session tracking if set to true.
enableURLRewriting	true	Enables URL rewriting. This provides session tracking via URL rewriting when the browser does not accept cookies. You must also use an encodeURL or encodeRedirectURL call in the servlet or JavaServer Pages™ (JSP™) page.
idLengthBytes	128	Specifies the number of bytes in this web module's session ID.

ssl

Defines SSL (Secure Socket Layer) parameters.

An `ssl` element is required inside an `http-listener` or `iiop-listener` element that has its `security-enabled` attribute set to `on`.

The grandparent “[http-service](#)” on page 76 element has properties that configure global SSL settings.

Superelements

[“http-listener” on page 71](#), [“iiop-listener” on page 79](#), [“jmx-connector” on page 94](#), [“ssl-client-config” on page 138](#)

Subelements

none

Attributes

The following table describes attributes for the `ssl` element.

TABLE 1–174 `ssl` Attributes

Attribute	Default	Description
<code>cert-nickname</code>	<code>slas</code>	The nickname of the server certificate in the certificate database or the PKCS#11 token. In the certificate, the name format is <code>tokenname:nickname</code> . Including the <code>tokenname:</code> part of the name in this attribute is optional.
<code>ssl2-enabled</code>	<code>false</code>	(optional) Determines whether SSL2 is enabled. If both SSL2 and SSL3 are enabled for a “ virtual-server ” on page 146, the server tries SSL3 encryption first. If that fails, the server tries SSL2 encryption.

TABLE 1-174 *ssl* Attributes (*Continued*)

Attribute	Default	Description
<code>ssl2-ciphers</code>	<code>none</code>	(optional) A comma-separated list of the SSL2 ciphers used, with the prefix + to enable or - to disable, for example <code>+rc4</code> . Allowed values are <code>rc4</code> , <code>rc4export</code> , <code>rc2</code> , <code>rc2export</code> , <code>idea</code> , <code>des</code> , <code>dese3</code> .
<code>ssl3-enabled</code>	<code>true</code>	(optional) Determines whether SSL3 is enabled. The default is <code>true</code> . If both SSL2 and SSL3 are enabled for a “ virtual-server ” on page 146, the server tries SSL3 encryption first. If that fails, the server tries SSL2 encryption.
<code>ssl3-tls-ciphers</code>	<code>none</code>	(optional) A comma-separated list of the SSL3 ciphers used, with the prefix + to enable or - to disable, for example <code>+SSL_RSA_WITH_RC4_128_MD5</code> . Allowed values are <code>SSL_RSA_WITH_RC4_128_MD5</code> , <code>SSL_RSA_WITH_3DES_EDE_CBC_SHA</code> , <code>SSL_RSA_WITH_DES_CBC_SHA</code> , <code>SSL_RSA_EXPORT_WITH_RC4_40_MD5</code> , <code>SSL_RSA_WITH_NULL_MD5</code> , <code>SSL_RSA_WITH_RC4_128_SHA</code> , and <code>SSL_RSA_WITH_NULL_SHA</code> . Values available in previous releases are supported for backward compatibility.
<code>tls-enabled</code>	<code>true</code>	(optional) Determines whether TLS is enabled.
<code>tls-rollback-enabled</code>	<code>true</code>	(optional) Determines whether TLS rollback is enabled. TLS rollback should be enabled for Microsoft Internet Explorer 5.0 and 5.5. For more information, see the Sun GlassFish Enterprise Server v2.1.1 Administration Guide .
<code>client-auth-enabled</code>	<code>false</code>	(optional) Determines whether SSL3 client authentication is performed on every request, independent of ACL-based access control.

ssl-client-config

Defines SSL parameters for the ORB when it makes outbound SSL connections and behaves as a client.

Superelements

[“iiop-service” on page 80](#)

Subelements

The following table describes subelements for the `ssl-client-config` element.

TABLE 1-175 *ssl-client-config* Subelements

Element	Required	Description
“ssl” on page 137	only one	Defines SSL parameters.

store-properties

Specifies session persistence (storage) properties.

Superelements

[“session-manager” on page 135](#)

Subelements

The following table describes subelements for the `store-properties` element.

TABLE 1–176 `store-properties` Subelements

Element	Required	Description
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

TABLE 1–177 `store-properties` Attributes

Attribute	Default	Description
<code>directory</code>	<code>domain-dir /generated/jsp /j2ee-apps/appname/appname_war</code>	(optional) Specifies the absolute or relative pathname of the directory into which individual session files are written. A relative path is relative to the temporary work directory for this web application. Applicable only if the <code>persistence-type</code> attribute of the “web-container-availability” on page 152 element is <code>file</code> .
<code>reap-interval-in-seconds</code>	60	(optional) Not implemented. Use the <code>reap-interval-in-seconds</code> attribute of the “manager-properties” on page 108 element instead.

system-property

Specifies a system property. A system property defines a common value for a setting at one of these levels, from highest to lowest: [“domain” on page 53](#), [“cluster” on page 36](#), [“server” on page 132](#), or [“config” on page 40](#). A value set at a higher level can be overridden at a lower level. Some system properties are predefined; see [“system-property” on page 139](#). You can also create system properties using this element.

The following example shows the use of a predefined system property:

```
<log-service file="${com.sun.aas.instanceRoot}/logs/server.log">
  <module-log-levels admin=INFO .../>
</log-service>
```

The following example shows the creation and use of a system property:

```

<config name="config1">
  ...
  <http-service>
    ...
    <http-listener id="ls1" host="0.0.0.0" port="${ls1-port}"/>
    ...
  </http-service>
  ...
  <system-property name="ls1-port" value="8080"/>
</config>

```

Superelements

[“cluster” on page 36](#), [“config” on page 40](#), [“domain” on page 53](#), [“server” on page 132](#)

Subelements

The following table describes subelements for the `system-property` element.

TABLE 1–178 system-property Subelements

Element	Required	Description
“description” on page 51	zero or one	Contains a text description of this element.

Attributes

The following table describes attributes for the `system-property` element.

TABLE 1–179 system-property Attributes

Attribute	Default	Description
name	none	Specifies the name of the system property.
value	none	Specifies the value of the system property.

Properties

The following table lists predefined system properties.

TABLE 1–180 Predefined System Properties

Property	Default	Description
com.sun.aas.installRoot	depends on operating system	Specifies the directory where the Enterprise Server is installed.

TABLE 1–180 Predefined System Properties *(Continued)*

Property	Default	Description
com.sun.aas.instanceRoot	depends on operating system	Specifies the top level directory for a server instance.
com.sun.aas.hostName	none	Specifies the name of the host (machine).
com.sun.aas.javaRoot	depends on operating system	Specifies the installation directory for the Java runtime.
com.sun.aas.imqLib	depends on operating system	Specifies the library directory for the Sun GlassFish Message Queue software.
com.sun.aas.configName	server-config	Specifies the name of the “config” on page 40 used by a server instance.
com.sun.aas.instanceName	server1	Specifies the name of the server instance. This property is not used in the default configuration, but can be used to customize configuration.
com.sun.aas.clusterName	cluster1	Specifies the name of the cluster. This property is only set on clustered server instances. This property is not used in the default configuration, but can be used to customize configuration.
com.sun.aas.domainName	domain1	Specifies the name of the domain. This property is not used in the default configuration, but can be used to customize configuration.

T

thread-pool

Defines a thread pool.

Superelements

[“thread-pools” on page 142](#)

Subelements

none

Attributes

TABLE 1–181 thread-pool Attributes

Attribute	Default	Description
thread-pool-id	none	Specifies the thread pool ID.
min-thread-pool-size	0	(optional) Specifies the minimum number of threads in the pool. These are created when the thread pool is instantiated.
max-thread-pool-size	200	(optional) Specifies the maximum number of threads the pool can contain.
idle-thread-timeout-in-seconds	120	(optional) Specifies the amount of time after which idle threads are removed from the pool.
num-work-queues	1	(optional) Specifies the total number of work queues serviced by this thread pool.

thread-pools

Contains thread pools.

Superelements

[“config” on page 40](#)

Subelements

The following table describes subelements for the `thread-pools` element.

TABLE 1–182 thread-pools Subelements

Element	Required	Description
“thread-pool” on page 141	one or more	Defines a thread pool.

transaction-service

Configures the Java Transaction Service (JTS).

Superelements

[“config” on page 40](#)

Subelements

The following table describes subelements for the `transaction-service` element.

TABLE 1-183 transaction-service Subelements

Element	Required	Description
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

The following table describes attributes for the `transaction-service` element.

TABLE 1-184 transaction-service Attributes

Attribute	Default	Description
automatic-recovery	false (developer profile) true (cluster and enterprise profiles)	(optional) If true, the server instance attempts transaction recovery during startup.
timeout-in-seconds	0	(optional) Specifies the amount of time after which the transaction is aborted. If set to 0, the transaction never times out.
tx-log-dir	directory specified by the log-root attribute of the “domain” on page 53 element	(optional) Specifies the parent directory of the transaction log directory <i>instance-name/tx</i> . The directory in which the transaction logs are kept must be writable by the user account under which the server runs. A relative path is relative to the log-root attribute of the “domain” on page 53 element.
heuristic-decision	rollback	(optional) If the outcome of a distributed transaction cannot be determined because other participants are unreachable, this property determines the outcome. Allowed values are <code>rollback</code> and <code>commit</code> .
retry-timeout-in-seconds	600	(optional) Determines the retry time in the following scenarios: <ul style="list-style-type: none">■ At the transaction recovery time, if resources are unreachable.■ If there are any transient exceptions in the second phase of a two phase commit protocol. A negative value specifies infinite retries. A value of 0 (zero) specifies no retries. A positive value indicates the time after which a retry is attempted.
keypoint-interval	65536 (64 K)	(optional) Specifies the number of transactions between keypoint operations in the log. Keypoint operations reduce the size of the transaction log file by compressing it. A larger value for this attribute results in a larger transaction log file, but fewer keypoint operations and potentially better performance. A smaller value results in smaller log files, but slightly reduced performance due to the greater frequency of keypoint operations.

Properties

The following table describes properties for the `transaction-service` element.

TABLE 1–185 transaction-service Properties

Property	Default	Description
oracle-xa-recovery-workaround	true	If true, the Oracle XA Resource workaround is used in transaction recovery.
disable-distributed-transaction-logging	false	If true, disables transaction logging, which might improve performance. If the automatic-recovery attribute is set to true, this property is ignored.
xaresource-txn-timeout	specific to the XAResource used	Changes the XAResource timeout. In some cases, the XAResource default timeout can cause transactions to be aborted, so it is desirable to change it.
pending-txn-cleanup-interval	none if this property is absent, 60 if this property is present but has no value	Specifies the interval, in seconds, at which an asynchronous thread checks for pending transactions and completes them.
use-last-agent-optimization	true	If true, enables last agent optimization, which improves the throughput of transactions. If one non-XA resource is used with XA resources in the same transaction, the non XA resource is the last agent.
delegated-recovery	false	If true, cluster-wide delegated recovery is enabled. You must also facilitate storing of transaction logs in a shared file system in one of these ways: <ul style="list-style-type: none"> ■ Set the “domain” on page 53 element’s log-root attribute to a shared file system base directory and set the tx-log-dir attribute to a relative path. ■ Set tx-log-dir to an absolute path to a shared file system directory, in which case log-root is ignored for transaction logs. ■ Set a “system-property” on page 139 called TX-LOG-DIR to a shared file system directory. For example: <pre><server config-ref="server-config" name="server"> <system-property name="TX-LOG-DIR" value="/net/tulsa/nodeagents/na/instance1/logs"/> </server></pre>
wait-time-before-recovery-insec	60	Specifies the wait time, in seconds, after which an instance starts the recovery for a dead instance.
db-logging-resource	none	Specifies the JNDI name of the JDBC resource for the database to which transactions are logged. For more information, see Chapter 16, “Using the Transaction Service,” in <i>Sun GlassFish Enterprise Server v2.1.1 Developer’s Guide</i> .
xa-servername	host name on which the Enterprise Server runs	Specifies the host name that the transaction service uses to identify transactions being managed by the installed Enterprise Server. This can sometimes be useful for recovering transactions from the log file that was created on a different host running the Enterprise Server. This should also be used when the Enterprise Server is installed as part of Sun Cluster HA.

transformation-rule

Configures an eXtensible Stylesheet Language Transformation (XSLT) rule, which transforms a web service message.

Superelements

[“web-service-endpoint” on page 157](#)

Subelements

The following table describes subelements for the `transformation-rule` element.

TABLE 1-186 `transformation-rule` Subelements

Element	Required	Description
“description” on page 51	zero or one	Contains a text description of this element.

Attributes

The following table describes attributes for the `transformation-rule` element.

TABLE 1-187 `transformation-rule` Attributes

Attribute	Default	Description
<code>name</code>	none	The name of the rule.
<code>enabled</code>	true	(optional) Determines whether the rule is enabled.
<code>apply-to</code>	<code>request</code>	(optional) Specifies whether the rule is applied to the request, the response, or both. Allowed values are: <ul style="list-style-type: none">■ <code>request</code> - Transformations are applied to the request in the order specified.■ <code>response</code> - Transformations are applied to the response in the order specified.■ <code>both</code> - Transformations are applied to both the request and the response. The order is reversed for the response.
<code>rule-file-location</code>	<code>domain-dir/generated/xml/app-or-module/xslt-file</code>	A fully qualified or relative path to the rule file that performs the transformation. Only XSLT files are allowed.

U

user-group

Contains the group to which the principal belongs.

Superelements

[“security-map” on page 130](#)

Subelements

none - contains data

V

virtual-server

Defines a virtual server. A virtual server, also called a virtual host, is a virtual web server that serves content targeted for a specific URL. Multiple virtual servers can serve content using the same or different host names, port numbers, or IP addresses. The HTTP service can direct incoming web requests to different virtual servers based on the URL.

When the Enterprise Server is first installed, a default virtual server is created. (You can also assign a default virtual server to each new [“http-listener” on page 71](#) you create.)

Note – Virtual servers are not the same thing as server instances. Each server instance is a completely separate server that contains one or more virtual servers.

Before the Enterprise Server can process a request, it must accept the request via a listener, then direct the request to the correct virtual server. The virtual server is determined as follows:

- If the listener is configured to only a default virtual server, that virtual server is selected.
- If the listener has more than one virtual server configured to it, the request Host header is matched to the hosts attribute of a virtual server. If no Host header is present or no hosts attribute matches, the default virtual server for the listener is selected.

If a virtual server is configured to an SSL listener, its hosts attribute is checked against the subject pattern of the certificate at server startup, and a warning is generated and written to the server log if they don’t match.

Superelements

[“http-service” on page 76](#)

Subelements

The following table describes subelements for the `virtual-server` element.

TABLE 1-188 `virtual-server` Subelements

Element	Required	Description
“http-access-log” on page 69	zero or one	Defines an access log file.
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

The following table describes attributes for the `virtual-server` element.

TABLE 1-189 `virtual-server` Attributes

Attribute	Default	Description
<code>id</code>	none	Virtual server ID. This is a unique ID that allows lookup of a specific virtual server. A virtual server ID cannot begin with a number.
<code>http-listeners</code>	none	(optional) In a comma-separated list, references <code>id</code> attributes of “http-listener” on page 71 elements that specify the connection(s) the virtual server uses. Required only for a <code>virtual-server</code> that is not referenced by the <code>default-virtual-server</code> attribute of an <code>http-listener</code> .
<code>default-web-module</code>	none	(optional) References the name attribute of the default “web-module” on page 155 for this virtual server, which responds to requests that cannot be resolved to other web modules deployed to this virtual server (see the “application-ref” on page 27 element).
<code>hosts</code>	none	A comma-separated list of values, each of which selects the current virtual server when included in the <code>Host</code> request header. Two or more <code>virtual-server</code> elements that reference or are referenced by the same <code>http-listener</code> cannot have any <code>hosts</code> values in common.
<code>state</code>	on	(optional) Determines whether a <code>virtual-server</code> is active (on) or inactive (off, disabled). The default is on (active). When inactive, a <code>virtual-server</code> does not service requests. If a <code>virtual-server</code> is disabled, only the global server administrator can turn it on.
<code>docroot</code>	none	(optional) Specifies the document root for this virtual server.

TABLE 1-189 virtual-server Attributes (Continued)

Attribute	Default	Description
log-file	server.log in the directory specified by the log-root attribute of the “domain” on page 53 element	(optional) Writes this virtual server’s log messages to a log file separate from the server log. The file and directory in which the virtual server log is kept must be writable by the user account under which the server runs. See the “log-service” on page 102 description for details about logs.

Properties

The following table describes properties for the `virtual-server` element.

TABLE 1-190 virtual-server Properties

Property	Default	Description
sso-enabled	false (developer and cluster profiles) true (enterprise profile)	If true, single sign-on is enabled for web applications on this virtual server that are configured for the same realm. If false, single sign-on is disabled for this virtual server, and users must authenticate separately to every application on the virtual server. This setting overrides the sso-enabled property setting of the “http-service” on page 76 element.
sso-max-inactive -seconds	300	Specifies the time after which a user’s single sign-on record becomes eligible for purging if no client activity is received. Since single sign-on applies across several applications on the same virtual server, access to any of the applications keeps the single sign-on record active. Higher values provide longer single sign-on persistence for the users at the expense of more memory use on the server.
sso-reap-interval -seconds	60	Specifies the interval between purges of expired single sign-on records.
setCacheControl	none	Specifies a comma-separated list of Cache-Control response directives. For a list of valid directives, see section 14.9 of the document at http://www.ietf.org/rfc/rfc2616.txt .
accessLogging Enabled	false (developer and cluster profiles) true (enterprise profile)	If true, enables access logging for this virtual server only. If false, disables access logging for this virtual server only.
accessLogBufferSize	32768	Specifies the size, in bytes, of the buffer where access log calls are stored. If the value is less than 5120, a warning message is issued, and the value is set to 5120. To set this property for all virtual servers, set it as a property of the parent “http-service” on page 76 element.

TABLE 1-190 virtual-server Properties *(Continued)*

Property	Default	Description
accessLogWriterInterval	300	Specifies the number of seconds before the log is written to the disk. The access log is written when the buffer is full or when the interval expires. If the value is 0, the buffer is always written even if it is not full. This means that each time the server is accessed, the log message is stored directly to the file. To set this property for all virtual servers, set it as a property of the parent “ http-service ” on page 76 element.
allowRemoteAddress	none	Specifies a comma-separated list of regular expression patterns that the remote client's IP address is compared to. If this property is specified, the remote address <i>must</i> match for this request to be accepted. If this property is not specified, all requests are accepted <i>unless</i> the remote address matches a denyRemoteAddress pattern.
denyRemoteAddress	none	Specifies a comma-separated list of regular expression patterns that the remote client's IP address is compared to. If this property is specified, the remote address <i>must not</i> match for this request to be accepted. If this property is not specified, request acceptance is governed solely by the allowRemoteAddress property.
allowRemoteHost	none	Specifies a comma-separated list of regular expression patterns that the remote client's hostname (as returned by <code>[java.net.]Socket.getInetAddress().getHostName()</code>) is compared to. If this property is specified, the remote hostname <i>must</i> match for this request to be accepted. If this property is not specified, all requests are accepted <i>unless</i> the remote hostname matches a denyRemoteHost pattern.
denyRemoteHost	none	Specifies a comma-separated list of regular expression patterns that the remote client's hostname (as returned by <code>[java.net.]Socket.getInetAddress().getHostName()</code>) is compared to. If this property is specified, the remote hostname <i>must not</i> match for this request to be accepted. If this property is not specified, request acceptance is governed solely by the allowRemoteHost property.
authRealm	none	Specifies the name attribute of an “ auth-realm ” on page 29 element, which overrides the server instance's default realm for stand-alone web applications deployed to this virtual server. A realm defined in a stand-alone web application's <code>web.xml</code> file overrides the virtual server's realm.
securePagesWithPragma	true	<p>Set this property to <code>false</code> to ensure that for all web applications on this virtual server file downloads using SSL work properly in Internet Explorer.</p> <p>You can set this property for a specific web application. For details, see “sun-web-app” in <i>Sun GlassFish Enterprise Server v2.1.1 Application Deployment Guide</i>.</p>

TABLE 1-190 virtual-server Properties (Continued)

Property	Default	Description
alternatedocroot_n	none	<p>Specifies an alternate document root (docroot), where <i>n</i> is a positive integer that allows specification of more than one. Alternate docroots allow web applications to serve requests for certain resources from outside their own docroot, based on whether those requests match one (or more) of the URI patterns of the web application's alternate docroots.</p> <p>If a request matches an alternate docroot's URI pattern, it is mapped to the alternate docroot by appending the request URI (minus the web application's context root) to the alternate docroot's physical location (directory). If a request matches multiple URI patterns, the alternate docroot is determined according to the following precedence order:</p> <ul style="list-style-type: none"> ■ Exact match ■ Longest path match ■ Extension match <p>For example, the following properties specify three alternate docroots. The URI pattern of the first alternate docroot uses an exact match, whereas the URI patterns of the second and third alternate docroots use extension and longest path prefix matches, respectively.</p> <pre><property name="alternatedocroot_1" value="from=/my.jpg dir=/srv/images/jpg"/> <property name="alternatedocroot_2" value="from=*.jpg dir=/srv/images/jpg"/> <property name="alternatedocroot_3" value="from=/jpg/* dir=/src/images"/></pre> <p>The value of each alternate docroot has two components: The first component, <code>from</code>, specifies the alternate docroot's URI pattern, and the second component, <code>dir</code>, specifies the alternate docroot's physical location (directory). Spaces are allowed in the <code>dir</code> component.</p> <p>You can set this property for a specific web application. For details, see “sun-web-app” in <i>Sun GlassFish Enterprise Server v2.1.1 Application Deployment Guide</i>.</p>
contextXmlDefault	none	Specifies the location, relative to <code>domain-dir</code> , of the <code>context.xml</code> file for this virtual server, if one is used. For more information about the <code>context.xml</code> file, see The Context Container (http://tomcat.apache.org/tomcat-5.5-doc/config/context.html).
allowLinking	false	<p>If true, resources that are symbolic links in web applications on this virtual server are served. The value of this property in the <code>sun-web.xml</code> file takes precedence if defined. For details, see “sun-web-app” in <i>Sun GlassFish Enterprise Server v2.1.1 Application Deployment Guide</i>.</p> <p>Caution – Setting this property to true on Windows systems exposes JSP source code.</p>

TABLE 1-190 virtual-server Properties *(Continued)*

Property	Default	Description
send-error_n	none	<p>Specifies custom error page mappings for the virtual server, which are inherited by all web applications deployed on the virtual server. A web application can override these custom error page mappings in its <code>web.xml</code> deployment descriptor. The value of each <code>send-error_n</code> property has three components, which may be specified in any order:</p> <p>The first component, <code>code</code>, specifies the three-digit HTTP response status code for which the custom error page should be returned in the response.</p> <p>The second component, <code>path</code>, specifies the absolute or relative file system path of the custom error page. A relative file system path is interpreted as relative to the <code>domain-dir/config</code> directory.</p> <p>The third component, <code>reason</code>, is optional and specifies the text of the reason string (such as <code>Unauthorized</code> or <code>Forbidden</code>) to be returned.</p> <p>For example:</p> <pre><property name="send-error_1" value="code=401 path=/myhost/401.html reason=MY-401-REASON"/></pre> <p>This example property definition causes the contents of <code>/myhost/401.html</code> to be returned with 401 responses, along with this response line:</p> <p>HTTP/1.1 401 MY-401-REASON</p>
redirect_n	none	<p>Specifies that a request for an old URL is treated as a request for a new URL. These properties are inherited by all web applications deployed on the virtual server. The value of each <code>redirect_n</code> property has two components, which may be specified in any order:</p> <p>The first component, <code>from</code>, specifies the prefix of the requested URI to match.</p> <p>The second component, <code>url-prefix</code>, specifies the new URL prefix to return to the client. The <code>from</code> prefix is simply replaced by this URL prefix.</p> <p>For example:</p> <pre><property name="redirect_1" value="from=/dummy url-prefix=http://etude"/></pre>

W

web-container

Configures the web container.

Superelements

[“config” on page 40](#)

Subelements

The following table describes subelements for the `web-container` element.

TABLE 1-191 web-container Subelements

Element	Required	Description
“session-config” on page 135	zero or one	Specifies session configuration information for the web container.
“property” on page 121	zero or more	Specifies a property or a variable.

Properties

The following table describes properties for the `web-container` element.

TABLE 1-192 web-container Properties

Property	Default	Description
<code>dispatcher-max-depth</code>	20	Prevents recursive <code>include</code> or <code>forward</code> statements from creating an infinite loop by setting a maximum nested dispatch level. If this level is exceeded, the following message is written to the server log: <code>Exceeded maximum depth for nested request dispatches</code>

web-container-availability

Enables availability in the web container, including HTTP session persistence. If HADB is installed and you have selected the enterprise profile, sessions are persisted to the HADB.

If availability is disabled, there is no high availability for HTTP session persistence. In other words, `persistence-type=memory`.

If availability is enabled but no other `web-container-availability` attributes are specified, the default session persistence configuration is as follows:

```
persistence-type=replicated
persistence-frequency=time-based
persistence-scope=session
```

If HADB is installed and you have selected the enterprise profile, the default persistence type is ha.

The default configuration for all applications can be changed by setting the various `web-container-availability` attributes and properties.

You can override the various web-container-availability attributes and properties for a specific application in sun-web.xml. For details, see the *Sun GlassFish Enterprise Server v2.1.1 Developer's Guide*.

For additional replicated session persistence properties you can set, see “availability-service” on page 32.

Superelements

[“availability-service” on page 32](#)

Subelements

The following table describes subelements for the web-container-availability element.

TABLE 1-193 web-container-availability Subelements

Element	Required	Description
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

The following table describes attributes for the web-container-availability element.

TABLE 1-194 web-container-availability Attributes

Attribute	Default	Description
availability-enabled	true	(optional) If set to true, and if availability is enabled for the server instance (see “availability-service” on page 32), high-availability features apply to all web applications deployed to the server instance that do not have availability disabled. All instances in a cluster should have the same availability value to ensure consistent behavior.

TABLE 1-194 web-container-availability Attributes *(Continued)*

Attribute	Default	Description
persistence-type	memory (availability disabled) replicated (availability enabled)	<p>(optional) Specifies the session persistence mechanism for web applications that have availability enabled. Allowed values are <code>memory</code> (no persistence), <code>file</code> (the file system) and <code>replicated</code> (other servers). If HADB is installed and you have selected the enterprise profile, you can also specify <code>ha</code>. For production environments that require session persistence, use <code>ha</code>.</p> <p>If set to <code>memory</code>, the “manager-properties” on page 108 element’s <code>session-file-name</code> attribute specifies the file system location where the HTTP session state is stored if the server instance is gracefully shut down. This is useful for internal testing but is not supported for production environments.</p> <p>If set to <code>file</code>, the “store-properties” on page 139 element’s <code>directory</code> attribute specifies the file system location where the HTTP session state is stored. Persisting to the file system is useful for internal testing but is not supported for production environments.</p>
persistence-frequency	web-method	<p>(optional) Specifies how often the session state is stored. Applicable only if the <code>persistence-type</code> is <code>replicated</code> or <code>ha</code>. Allowed values are as follows:</p> <ul style="list-style-type: none"> ■ <code>web-method</code> - The session state is stored at the end of each web request prior to sending a response back to the client. This mode provides the best guarantee that the session state is fully updated in case of failure. ■ <code>time-based</code> - The session state is stored in the background at the frequency set by the “manager-properties” on page 108 element’s <code>reap-interval-in-seconds</code> attribute. This mode provides less of a guarantee that the session state is fully updated. However, it can provide a significant performance improvement because the state is not stored after each request.
persistence-scope	session	<p>(optional) Specifies how much of the session state is stored. Applicable only if the <code>persistence-type</code> is <code>replicated</code> or <code>ha</code>. Allowed values are as follows:</p> <ul style="list-style-type: none"> ■ <code>session</code> - The entire session state is stored every time. This mode provides the best guarantee that your session data is correctly stored for any distributable web application. ■ <code>modified-session</code> - The entire session state is stored if it has been modified. A session is considered to have been modified if <code>HttpSession.setAttribute()</code> or <code>HttpSession.removeAttribute()</code> was called. You must guarantee that <code>setAttribute()</code> is called every time an attribute is changed. This is not a Java EE specification requirement, but it is required for this mode to work properly. ■ <code>modified-attribute</code> - Only modified session attributes are stored. For this mode to work properly, you must follow some guidelines, which are explained immediately following this table.
sso-failover-enabled	false	(optional) If true, the single sign-on state is highly available. To enable single sign-on, use the <code>sso-enabled</code> property of the “ virtual-server ” on page 146 element.

TABLE 1-194 web-container-availability Attributes *(Continued)*

Attribute	Default	Description
http-session-store-pool-name	"availability-service" on page 32 store-pool-name attribute value	(optional) Specifies the jndi-name of the "jdbc-resource" on page 89 used for connections to the HADB for session persistence. Applicable if HADB is installed and you have selected the enterprise profile. For more information about setting up a connection pool and JDBC resource for the HADB, see the description of the configure-ha-cluster command in the Sun GlassFish Enterprise Server v2.1.1 Reference Manual .

If the `persistence-scope` attribute is set to `modified-attribute`, your web application must follow these guidelines:

- Call `setAttribute()` every time the session state is modified.
- Make sure there are no cross-references between attributes. The object graph under each distinct attribute key is serialized and stored separately. If there are any object cross references between the objects under each separate key, they are not serialized and deserialized correctly.
- Distribute the session state across multiple attributes, or at least between a read-only attribute and a modifiable attribute.

Properties

The following table describes properties for the `web-container-availability` element.

TABLE 1-195 web-container-availability Properties

Property	Default	Description
uuid-impl-class	none	Specifies the name of the class that generates session IDs. If this property is not specified, the Enterprise Server's internal session ID generator is used. It is the developer's responsibility to ensure that generated IDs are universally unique even when running on multiple JVMs on multiple machines in a cluster. Failure to ensure this in the algorithm results in nondeterministic behavior and likely corruption of HTTP session data.

web-module

Specifies a deployed web module.

Superelements

["applications" on page 28](#)

Subelements

The following table describes subelements for the `web-module` element.

TABLE 1–196 web-module Subelements

Element	Required	Description
“description” on page 51	zero or one	Contains a text description of this element.
“web-service-endpoint” on page 157	zero or more	Configures a web service endpoint.
“property” on page 121	zero or more	Specifies a property or a variable.

Attributes

The following table describes attributes for the `web-module` element.

TABLE 1–197 web-module Attributes

Attribute	Default	Description
name	none	The name of the web module.
context-root	none	<p>The context root at which the web module is deployed. The context root can be the empty string or just /. The context root can start with the / character, but doesn't have to.</p> <p>For load balancing to work, web module context roots must be unique within a cluster. See the Sun GlassFish Enterprise Server v2.1.1 High Availability Administration Guide for more information about load balancing.</p> <p>Note – Some topics in the documentation pertain to features that are available only in domains that are configured to support clusters. Examples of domains that support clusters are domains that are created with the cluster profile or the enterprise profile. For information about profiles, see “Usage Profiles” in Sun GlassFish Enterprise Server v2.1.1 Administration Guide.</p>
location	none	<p>A fully qualified or relative path to the directory to which the contents of the .war file have been extracted. If relative, it is relative to the following directory:</p> <p><i>domain-dir/applications/j2ee-modules/</i></p>
object-type	user	<p>(optional) Defines the type of the resource. Allowed values are:</p> <ul style="list-style-type: none"> ■ <code>system-all</code> - A system resource for all server instances and the domain application server. ■ <code>system-admin</code> - A system resource only for the domain application server. ■ <code>system-instance</code> - A system resource for all server instances only. ■ <code>user</code> - A user resource.
enabled	true	(optional) Determines whether the web module is enabled.
libraries	none	(optional) Specifies an absolute or relative path to libraries specific to this module or application. A relative path is relative to <i>domain-dir/lib/applibs</i> . If the path is absolute, the path must be accessible to the domain administration server (DAS), which means it must be under <i>domain-dir</i> . To include more than one path, use a system-specific separator, such as a colon for Solaris or a semicolon for Windows. The libraries are made available to the application in the order in which they are specified.

TABLE 1-197 web-module Attributes *(Continued)*

Attribute	Default	Description
availability-enabled	false	(optional) Specifies whether availability is enabled in this web application for HTTP session persistence (and potentially passivation). Availability must also be enabled for the application or stand-alone web module during deployment. For more information about availability, see “ availability-service ” on page 32 .
directory-deployed	false	(optional) Specifies whether the application has been deployed as a directory.

web-service-endpoint

Configures a web service endpoint, which can be a JAX-RPC/JAXWS 2.0 or JSR-109 web service.

Superelements

[“ejb-module” on page 57](#), [“j2ee-application” on page 81](#), [“web-module” on page 155](#)

Subelements

The following table describes subelements for the web-service-endpoint element.

TABLE 1-198 web-service-endpoint Subelements

Element	Required	Description
“registry-location” on page 125	zero or more	Specifies the registry where web service endpoint artifacts are published.
“transformation-rule” on page 145	zero or more	Configures an eXtensible Stylesheet Language Transformation (XSLT) rule.

Attributes

The following table describes attributes for the web-service-endpoint element.

TABLE 1–199 web-service-endpoint Attributes

Attribute	Default	Description
name	none	The fully qualified name of the web service. For a web service endpoint within an application, the format is as follows: <i>module-name#endpoint-name</i> For example: <code>jaxrpc-simple.war#HelloIF</code> For a web service endpoint that is a stand-alone module, the name is just the <i>endpoint-name</i> .
monitoring	OFF	(optional) Specifies the monitoring level for this web service. For information about monitoring levels, see “ module-monitoring-levels ” on page 114.
max-history-size	25	(optional) Specifies the maximum number of monitoring records stored for this endpoint.
jbi-enabled	false	(optional) Determines whether the visibility of this endpoint as a Java Business Integration service is enabled or disabled.

Index

A

acceptor-queue-length property, 73, 77
acceptor-threads attribute, 72
access-log element, 22-23
access log file, 102
accessLogBufferSize property, 79, 148
accessLoggingEnabled property, 78, 148
accessLogWriterInterval property, 79, 149
action element, 23
action-mbean-name attribute, 23
activate-default-principal-to-role-mapping attribute, 132
address attribute, 72, 80, 95
addresslist-behavior attribute, 93
addresslist-iterations attribute, 93
AddressList property, 45
admin-object-resource element, 23-24
admin-password attribute, 92
admin-service element, 24-25
admin-session-timeout-in-minutes attribute, 51
admin-user-name attribute, 92
alert-service element, 25-26
alert-subscription element, 26
allow-non-component-callers attribute, 87
allowLinking property, 150
allowRemoteAddress property, 149
allowRemoteHost property, 149
alternatedocroot_n property, 150
anonymous-role attribute, 131
appclient-module element, 26-27
append-version property, 94
application-ref element, 27-28

application-root attribute, 54
applications, location, 54
applications element, 28-29
apply-to attribute, 145
assign-groups property, 31
associate-with-thread attribute, 45, 88
AssociateWithThread property, 46, 89
audit-enabled attribute, 132
audit-module element, 29
audit-modules attribute, 132
auth-layer attribute, 112
auth-realm element, 29-32
auth-realm-name attribute, 95
auth-recipient attribute, 126, 130
auth-source attribute, 126, 130
authPassthroughEnabled property, 73, 77
authRealm property, 149
auto-apply-enabled attribute, 101
auto-manage-ha-store attribute, 34
autodeploy-dir attribute, 51
autodeploy-enabled attribute, 51
autodeploy-jsp-precompilation-enabled attribute, 51
autodeploy-polling-interval-in-seconds attribute, 51
autodeploy-verifier-enabled attribute, 51
automatic-recovery attribute, 143
availability-enabled attribute
 availability-service element, 33
 ejb-container-availability element, 57
 ejb-module element, 58
 extension-module element, 65
 j2ee-application element, 82
 jms-availability element, 91

availability-enabled attribute (*Continued*)
 web-container-availability element, 153
 web-module element, 157
availability-service element, 32-35

B

backend-principal element, 35
base-dn property, 31
blocking-enabled attribute, 72
bufferSize property, 74, 78
bytecode-preprocessors attribute, 84

C

cache-idle-timeout-in-seconds attribute, 56
cache-resize-quantity attribute, 55
callerPrincipal property, 64
capture-app-dd attribute, 53
capture-hadb-info attribute, 53
capture-install-log attribute, 52
capture-system-info attribute, 52
cert nickname attribute, 137
certificates, 31
charset property, 32
class-name attribute
 lifecycle-module element, 99
 provider-config element, 124
classname attribute, 29, 30
classpath attribute, 99, 121
classpath-prefix attribute, 84
classpath-suffix attribute, 84
client-auth-enabled attribute, 138
client-authentication-required attribute, 81
ClientId property, 45
cluster element, 36-38
cluster-ref element, 38-39
clusters element, 39-40
CMP, 119
cmt-max-runtime-exceptions property, 111
cometSupport property, 74
commit-option attribute, 56
componentName property, 64

compressableMimeType property, 74
compression property, 74
compute-checksum attribute, 52
config element, 40-41
config-ref attribute, 37, 133
configs element, 41-42
connection-creation-retry-attempts attribute, 44, 87
connection-creation-retry-interval-in-seconds
 attribute, 44, 87
connection-definition-name attribute, 43
connection-leak-reclaim attribute, 44, 87
connection-leak-timeout-in-seconds attribute, 44, 87
connection-pool element, 42
connection-validation-method attribute, 87
connectionTimeout property, 74, 78
connectionUploadTimeout property, 75, 79
connector-connection-pool element, 42-46
connector-module element, 46-47
connector-resource element, 47-48
connector-resource-jndi-name attribute, 125
connector-service element, 48-49
container-managed persistence, 119-120
context-root attribute, 156
context.xml file, 150
contextXmlDefault property, 150
cpu-http-threshold attribute, 118
cpu-mm-threshold attribute, 118
cpu-overload-activation-algorithm attribute, 119
cpu-overload-deactivation-algorithm attribute, 119
cpu-overload-protection attribute, 118
crlFile property, 75
custom-resource element, 49-50

D

das-config element, 50-51
databaseName property, 88
datasource-classname attribute, 85
datasource-jndi property, 31
datasourceName property, 89
dateString property, 63
db-logging-resource property, 144
db-password property, 32
db-user property, 31

debug-enabled attribute, 84
 debug-options attribute, 84
 debug property, 124
 default-client-provider attribute, 112
 default-jms-host attribute, 93
 default-principal attribute, 131
 default-principal-password attribute, 131
 default-provider attribute, 112
 default-realm attribute, 131
 default-response-type attribute, 76
 default-type attribute, 76
 default virtual server
 for an http-listener element, 72
 for the entire server, 146
 default-virtual-server attribute, 72
 default-web-module attribute, 147
 delegated-recovery property, 144
 denyRemoteAddress property, 149
 denyRemoteHost property, 149
 deploy-xml-validation attribute, 51
 description element, 51-52
 description property, 89
 device-admin-port property, 101
 device-host property, 101
 diagnostic-service element, 52-53
 differenceMode property, 63
 digest-algorithm property, 32
 directory attribute, 139
 directory-deployed attribute
 appclient-module element, 27
 connector-module element, 47
 ejb-module element, 58
 extension-module element, 65
 j2ee-application element, 82
 web-module element, 157
 directory property, 31
 disable-distributed-transaction-logging property, 144
 disable-timeout-in-minutes attribute, 28, 134
 disableUploadTimeout property, 75, 79
 discovery-timeout-in-millis attribute, 68
 dispatcher-max-depth property, 152
 dns-lookup-enabled attribute, 76
 docroot attribute, 147
 domain element, 53-54

domain.xml file
 DTD file for, 16
 element hierarchy, 18-21
 elements in, 21
 location, 15-21
 dynamic-reconfiguration-enabled attribute, 41
 dynamic-reload-enabled attribute, 51
 dynamic-reload-poll-interval-in-seconds attribute, 51
 dynamic.username.password property, 124

E

ejb-container-availability element, 56-57
 ejb-container element, 54-56
 ejb-module element, 57-59
 ejb-timer-service element, 59
 elements
 descriptions of, 21
 hierarchy, 18-21
 referencing, 18
 enableCookies property, 137
 enabled attribute, 118
 enableURLRewriting property, 137
 encoding property, 32
 encryption.key.alias property, 124
 env-classpath-ignored attribute, 85
 event element, 59-64
 event types, 61
 extension-module element, 64-65
 external-jndi-resource element, 65-66
 external-port attribute, 72

F

factory-class attribute, 49, 66, 120
 fail-all-connections attribute, 44, 87
 failure-detection-max-tries attribute, 68
 failure-detection-timeout-in-millis attribute, 68
 family attribute, 72
 file attribute, 103
 file-caching-enabled attribute, 70
 file property, 31
 file-transmission-enabled attribute, 71

filter-class-name attribute, 67
filter-config element, 66-67
forced-response-type attribute, 76
forced-type attribute, 76
format attribute, 22
format property, 104

G

globally-enabled attribute, 70
gms-bind-interface-address property, 38
granularityPeriod property, 62
group-base-dn property, 31
group-management-service element, 67-68
group-name-column property, 31
group-search-filter property, 31
group-table property, 31
group-target property, 31

H

ha-agent-hosts attribute, 33
ha-agent-password attribute, 33
ha-agent-port attribute, 33
ha-store-healthcheck-enabled attribute, 34
ha-store-healthcheck-interval-in-seconds attribute, 34
ha-store-name attribute, 33
hash-init-size attribute, 71
header-buffer-length-in-bytes attribute, 126
health-checker element, 68-69
heartbeat-address attribute, 37
heartbeat-enabled attribute, 37
heartbeat-port attribute, 37
heuristic-decision attribute, 143
highThreshold property, 63
host attribute, 92
hosts attribute, 147
 checking against subject pattern, 146
http-access-log element, 69-70
http-file-cache element, 70-71
HTTP listen socket, 71
http-listener element, 71-75
http-listeners attribute, 147

http-protocol element, 75-76
http-service element, 76-79
http-session-store-pool-name attribute, 155
https-routing attribute, 98

I

id attribute
 http-listener element, 71
 iiop-listener element, 80
 virtual-server element, 147
idle-thread-timeout-in-seconds attribute, 142
idle-timeout-in-seconds attribute, 44, 86, 111
idLengthBytes property, 137
iiop-listener element, 79-80
iiop-service element, 80-81
impl-class-name attribute, 110
init-timeout-in-seconds attribute, 92
initial-thread-count attribute, 126
initThreshold property, 63
instance-name property, 94
instance-name-suffix property, 94
INSTANCE-SYNC-JVM-OPTIONS property, 116
interval-in-seconds attribute, 69
ipAddress property, 64
iponly attribute, 70
is-connection-validation-required attribute, 44, 86
is-failure-fatal attribute, 99
is-isolation-level-guaranteed attribute, 86

J

j2ee-application element, 81-82
jaas-context property, 31
jacc attribute, 132
jacc-provider element, 82-83
Java Business Integration, 158
java-config element, 83-85
Java Database Connectivity, *See JDBC*
java-home attribute, 84
Java Naming and Directory Interface, *See JNDI*
Java Platform Debugger Architecture, *See JPDA*
Java Transaction Service, *See JTS*

Java Virtual Machine, *See* JVM
 java-web-start-enabled attribute, 27, 82
 javac-options attribute, 84
 JavaMail, 104
 JBI, *See* Java Business Integration
 jbi-enabled attribute, 158
 JDBC connection pool, 85-89
 jdbc-connection-pool element, 85-89
 JDBC resource, 89
 jdbc-resource element, 89-90
 jdbc-resource-jndi-name attribute, 120
 JMS, 91, 92
 jms-availability element, 90-91
 jms-host element, 91-92
 jms-service element, 92-94
 jmx-connector element, 94-96
 JNDI, 65
 jndi-lookup-name attribute, 66
 jndi-name attribute
 admin-objectresource element, 24
 custom-resource element, 49
 external-jndi-resource element, 66
 jdbc-resource element, 48, 90
 mail-resource element, 105
 persistence-manager-factory-resource element, 120
 JPDA debugging options, 84
 JTS, 142
 JVM, 83
 adding options to the server, 96
 jvm-options element, 96

K

keep-alive element, 96-97
 keypoint-interval attribute, 143

L

lazy-connection-association attribute, 44, 88
 lazy-connection-enlistment attribute, 44, 87
 LazyConnectionAssociation property, 46, 89
 LazyConnectionEnlistment property, 46, 89
 lb-config element, 97-98

lb-config-name attribute, 101
 lb-configs element, 98
 lb-enabled attribute, 28, 134
 lb-policy attribute, 39
 lb-policy-module attribute, 39
 lb-weight attribute, 133
 level attribute, 61
 level property, 62
 libraries attribute, 58, 65, 82, 156
 lifecycle-module element, 98-99
 listen socket, 71
 listener-class-name attribute, 100
 listener-config element, 99-100
 load-balancer element, 100-102
 load-balancers element, 102
 load balancing, 97-98, 156
 load-on-startup element in web.xml, 74
 load-order attribute, 99
 locale attribute, 54
 location attribute
 appclient-module element, 27
 connector-module element, 47
 ejb-module element, 58
 extension-module element, 65
 j2ee-application element, 82
 web-module element, 156
 log-directory attribute, 70
 log-file attribute, 148
 log-filter attribute, 103
 log-handler attribute, 103
 log levels, 112-114
 log-root attribute, 54
 log-rotation-limit-in-bytes attribute, 103
 log-rotation-timelimit-in-minutes attribute, 103
 log-service element, 102-104
 log-to-console attribute, 103
 logger names, 112-114
 loggerNames property, 62
 logging settings in domain.xml, 102-104
 lowThreshold property, 63

M

mail-resource element, 104-106

management-rule element, 106-107
management-rules element, 107-108
manager-properties element, 108-109
mapped-principal-class attribute, 132
match-connections attribute, 45, 88
MatchConnections property, 46, 89
max-age-in-seconds attribute, 70
max-buffered-messages property, 104
max-cache-size attribute, 55
max-connection-usage-count attribute, 45, 88
max-connections attribute, 97, 117
max-files-count attribute, 71
max-history-size attribute, 158
max-log-entries attribute, 53
max-pending-count attribute, 42
max-pool-size attribute, 43, 55, 86, 111
max-redeliveries attribute, 59
max-sessions attribute, 109
max-thread-pool-size attribute, 142
max-wait-time-in-millis attribute, 43, 86
maxKeepAliveRequests property, 74, 78
mbean element, 109-110
mdb-container element, 110-111
medium-file-size-limit-in-bytes attribute, 70
medium-file-space-in-bytes attribute, 70
mem-http-threshold attribute, 118
mem-mm-threshold attribute, 118
mem-overload-activation-algorithm attribute, 119
mem-overload-deactivation-algorithm attribute, 119
memory-overload-protection attribute, 118
message-driven beans, 110
message-fragment-size attribute, 117
message property, 64
message-security-config element, 111-112
min-log-level attribute, 53
min-thread-pool-size attribute, 142
minCompressionSize property, 75
minimum-delivery-interval-in-millis attribute, 59
mm-threshold-http-wait-time attribute, 119
module-log-levels element, 112-114
module-monitoring-levels element, 114-115
module-type attribute, extension-module element, 65
modulus property, 63
monitoring attribute, 158

monitoring-cache-enabled property, 77
monitoring-cache-refresh-in-millis property, 77
monitoring-enabled attribute, 98
monitoring-service element, 115
monitorType property, 62
mq-scheme attribute, 93
mq-service attribute, 94
mq-store-pool-name attribute, 91

N

name attribute, 26, 92, 95, 116
appclient-module element, 27
audit-module element, 29
auth-realm element, 30, 83
cluster element, 36
config element, 41
connector-connection-pool element, 43
connector-module element, 47
ejb-module element, 58
extension-module element, 65
j2ee-application element, 81
jdbc-connection-pool element, 85
lb-config element, 98
lifecycle-module element, 99
load-balancer element, 101
mbean element, 109
profiler element, 121
property element, 123
resource-adapter-config element, 127
security-map element, 130
server element, 133
system-property element, 140
transformation-rule element, 145
web-module element, 156
web-service-endpoint element, 158
name property, 61, 62, 64
native library path, configuring, 84
native-library-path attribute, 121
native-library-path-prefix attribute, 84
native-library-path-suffix attribute, 84
networkProtocol property, 89
noCompressionUserAgents property, 75
node-agent element, 115-116

node-agent-ref attribute, 133
 node-agents element, 116-117
 non-transactional-connections attribute, 87
 notifyDiffer property, 62
 notifyMatch property, 62
 num-work-queues attribute, 142
 number-of-samples attribute, 119
 numberOfOccurrences property, 64
 numberType property, 63

O

object-name attribute, 110
 object-type attribute
 admin-object-resource element, 24
 connector-module element, 47
 connector-resource element, 48
 custom-resource element, 50
 ejb-module element, 58
 extension-module element, 65
 external-jndi-resource element, 66
 j2ee-application element, 82
 jdbc-resource element, 90, 99
 mail-resource element, 105
 mbean element, 110
 persistence-manager-factory-resource element, 120
 resource-adapter-config element, 127
 web-module element, 156
 observedAttribute property, 62
 observedMbean property, 62
 observedObject property, 62
 offset property, 63
 oracle-xa-recovery-workaround property, 144
 orb element, 117-118
 overload-protection-service element, 118-119

P

password attribute, 35
 password-column property, 31
 Password property, 45
 password property, 88, 94
 pattern property, 63

pending-txn-cleanup-interval property, 144
 period property, 63
 persistence-frequency attribute, 154
 persistence-manager-factory-resource
 element, 119-120
 persistence-scope attribute, 154
 persistence-type attribute, 154
 policy-configuration-factory-provider attribute, 83
 policy-provider attribute, 83
 pool-idle-timeout-in-seconds attribute, 56
 pool-name attribute, 48, 90
 pool-resize-quantity attribute, 44, 55, 86, 111
 port attribute
 http-listener element, 72
 iiop-listener element, 80
 jms-host element, 92
 jmx-connector element, 95
 port property, 89
 principal element, 120
 profiler element, 121
 properties
 about, 121-123
 system, 139-141
 property element, 121-123
 protocol attribute, 95
 provider-config element, 123-124
 provider-id attribute, 124
 provider-type attribute, 124
 proxiedProtocol property, 74, 78
 proxyHandler property, 73, 78
 push-interval-in-seconds property, 104

Q

queue-size-in-bytes attribute, 42

R

reader-queue-length property, 73, 77
 reader-threads property, 73, 77
 reap-interval-in-seconds attribute, 108, 139
 receive-buffer-size-in-bytes attribute, 42
 reconnect-attempts attribute, 93

reconnect-enabled attribute, 93
reconnect-interval-in-seconds attribute, 93
record-event attribute, 61
recycle-objects property, 73, 77
redelivery-interval-internal-in-millis attribute, 59
redirect_n property, 151
redirect-port attribute, 72
ref attribute
 application-ref element, 28
 cluster-ref element, 39
 resource-ref element, 128
 server-ref element, 134
referencing elements, 18
registry-location element, 125
reload-poll-interval-in-seconds attribute, 98
removal-timeout-in-seconds attribute, 56
replication_measurement_enabled property, 34
replication_measurement_interval property, 35
request-policy element, 125-126
request-processing element, 126
request-timeout-in-seconds attribute, 126
res-adapter attribute, 24
res-type attribute, 24, 49, 66, 86
resource-adapter-config element, 126-127
resource-adapter-name attribute, 43, 127
resource adapters, 46-47
resource-ref element, 127-128
resources element, 128-129
response-policy element, 129-130
response-timeout-in-seconds attribute, 98
retain-error-statistics-for-hours attribute, 103
retry-after-interval attribute, 119
retry-timeout-in-seconds attribute, 143
rmic-options attribute, 84
roleName property, 89
rolling-upgrade-backup-directory property, 35
rotation-enabled attribute, 22
rotation-interval-in-minutes attribute, 22
rotation-policy attribute, 22
rotation-suffix attribute, 22
rule-file-location attribute, 145

S

sample-rate attribute, 118
search-bind-dn property, 31
search-bind-password property, 31
search-filter property, 31
Secure Socket Layer, *See SSL*
securePagesWithPragma property, 149
security, 131-132
security.config property, 124
security-enabled attribute, 72, 80, 95
security-map element, 130-131
security-service element, 131-132
self-management, 106-107
send-buffer-size-in-bytes attribute, 42
send-error_n property, 151
server-classpath attribute, 84
server element, 132-133
server log file, 54, 102-104
server-name attribute, 72
server-ref element, 133-134
serverName property, 62, 88
servers element, 134-135
session-config element, 135
session-file-name attribute, 108
session-id-generator-classname attribute, 109
session-manager element, 135-136
session-properties element, 136-137
session-store attribute, 56
session-timeout element, 136
setCacheControl property, 148
fsfb-ha-persistence-type attribute, 57
fsfb-persistence-type attribute, 57
fsfb-store-pool-name attribute, 57
shutdown-timeout-in-seconds attribute, 49
signature.key.alias property, 124
single sign-on, 79, 148
small-file-size-limit-in-bytes attribute, 71
small-file-space-in-bytes attribute, 71
sourceMBean property, 63
sourceObjectName property, 63
SSL, configuring, 137-138
ssl-cache-entries property, 77
ssl-client-config element, 138-139
ssl element, 137-138

ssl-enabled attribute, 76
 ssl-proxy-host property, 101
 ssl-proxy-port property, 102
 ssl-session-timeout property, 77
 ssl2-ciphers attribute, 138
 ssl2-enabled attribute, 137
 SSL3 client authentication, 138
 ssl3-enabled attribute, 138
 ssl3-session-timeout property, 77
 ssl3-tls-ciphers attribute, 138
 sso-enabled property, 79, 148
 sso-failover-enabled attribute, 154
 sso-max-inactive-seconds property, 148
 sso-reap-interval-seconds property, 148
 start-args attribute, 93
 start-servers-in-startup attribute, 116
 state attribute, 147
 statement-timeout-in-seconds attribute, 87
 steady-pool-size attribute, 43, 55, 86, 110
 store-pool-name attribute, 34
 store-properties element, 139
 store-protocol attribute, 105
 store-protocol-class attribute, 105
 stringToCompare property, 62
 subscribe-listener-with attribute, 100
 sun-domain_1_5.dtd file, 16
 Sun Java System Message Queue, 94
 System Classloader, 84
 system-classpath attribute, 84
 system-jmx-connector-name attribute, 25, 116
 system-property element, 139-141

T

thread-count attribute, 96, 126
 thread-increment attribute, 126
 thread-pool element, 141-142
 thread-pool-id attribute, 142
 thread-pool-ids attribute, 127
 thread-pools element, 142
 timeout-in-seconds attribute, 69, 97, 136, 143
 timer-datasource attribute, 59
 tls-enabled attribute, 138
 tls-rollback-enabled attribute, 138

traceEnabled property, 74, 78
 transaction-isolation-level attribute, 86
 transaction log file, 102, 143
 transaction-service element, 142-145
 transaction-support attribute, 44
 transformation-rule element, 145
 transport-protocol attribute, 105
 transport-protocol-class attribute, 105
 trustAlgorithm property, 75
 trustMaxCertLength property, 75
 tx-log-dir attribute, 143
 type attribute, 25, 61, 93
 type property, 63

U

uriEncoding property, 75, 79
 url attribute, 69
 url property, 89
 use-last-agent-optimization property, 144
 use-nio-direct-bytebuffer property, 73, 77
 use-system-logging attribute, 103
 use-thread-pool-ids attribute, 117
 user-group element, 146
 user-name attribute, 35
 user-name-column property, 31
 user-name property, 94
 user property, 88
 user-table property, 31
 UserName property, 45
 uuid-impl-class property, 155

V

validate-atmost-once-period-in-seconds attribute, 44, 87
 validation-table-name attribute, 87
 value attribute, 123, 140
 variables, 16-18
 verify-config attribute, 52
 verify-failure-timeout-in-millis attribute, 68
 version attribute, 76
 victim-selection-policy attribute, 56

virtual-server element, 146-151

virtual servers, log file for, 102

virtual-servers attribute, 28

W

wait-time-before-recovery-insec property, 144

web-container-availability element, 152-155

web-container element, 151-152

web module, default, 147

web-module element, 155-157

web-service-endpoint element, 157-158

web.xml file session-timeout element, 136

wrap-jdbc-objects attribute, 88

X

xa-servername property, 144

xaresource-txn-timeout property, 144

XML specification, 16

xpowered-by attribute, 72

XSLT, 145