

Oracle Endeca Platform Services

XML Reference

Version 6.1.3 • October 2012 • Revision A



Contents

Preface.....	9
About this guide.....	9
Who should use this guide.....	9
Conventions used in this guide.....	10
Contacting Oracle Support.....	10
Chapter 1: Endeca XML Reference.....	11
Welcome.....	11
Analytics_config.xml elements.....	11
Common.dtd elements.....	11
COMMENT.....	11
compression.....	12
CONFIG.....	13
DIMENSION_ID.....	14
DIMNAME.....	14
DVAL_ID.....	15
DVAL_PATH.....	15
KEY_DIMENSION.....	16
LOG.....	17
PHRASE.....	18
PROFILE.....	19
PROP.....	19
PROPNAM.....	20
PVAL.....	20
RECORD_GROUP.....	20
RECORD_ID.....	21
RECORD_INDEX.....	21
Derived_props.xml elements.....	22
DERIVED_PROP.....	22
DERIVED_PROPS.....	23
Dimensions.xml elements.....	23
BOUND.....	24
DIMENSION.....	25
DIMENSIONS.....	26
DIMENSION_NODE.....	27
DVAL.....	28
LBOUND.....	29
NUM_DVALS.....	30
SYN.....	30
UBOUND.....	31
Dimension_groups.xml elements.....	32
DIMENSION_GROUP.....	32
DIMENSION_GROUPS.....	33
Dimension_refs.xml elements.....	34
DIMENSION_REF.....	34
DIMENSION_REFS.....	35
Dimsearch_config.xml elements.....	36
DIMSEARCH_CONFIG.....	36
Dimsearch_index.xml elements.....	37
DIMSEARCH_HIERARCHY.....	37
DIMSEARCH_INDEX.....	38
Dval_ranks.xml elements.....	40
DVAL_RANK.....	40
DVAL_RANKS.....	41
Dval_refs.xml elements.....	42
DVAL_REF.....	42
DVAL_REFS.....	43
Externaldimension elements.....	44

Key_props.xml elements.....	44
Languages.xml elements.....	44
KEY_LANGUAGE.....	44
LANGUAGES.....	45
Phrases.xml elements.....	46
PHRASES.....	46
PHRASE_ADDITIONS.....	47
DIMENSION_IMPORTS.....	48
Pipeline.epx elements.....	48
DIMENSION_ADAPTER.....	49
DIMENSION_SERVER.....	51
DIMENSION_SOURCE.....	52
DVAL_ID_LIMITS.....	53
EXPRBODY.....	54
EXPRESSION.....	54
EXPRNODE.....	56
ID_SERVER.....	57
INDEXER_ADAPTER.....	58
JAVA_MANIPULATOR.....	61
JOIN_ENTRY.....	62
PASS_THROUGH.....	63
PERL_MANIPULATOR.....	65
PERL_METHOD.....	68
PIPELINE.....	69
PROP_MAPPER.....	72
PROP_MAPPING_DIM.....	74
PROP_MAPPING_NONE.....	76
PROP_MAPPING_PROP.....	76
RECORD_ADAPTER.....	78
RECORD_ASSEMBLER.....	84
RECORD_CACHE.....	85
RECORD_JOIN.....	87
RECORD_MANIPULATOR.....	88
RECORD_SOURCE.....	89
ROLLOVER.....	89
TRANSFORMER.....	91
UPDATE_ADAPTER.....	92
Precedence_rules.xml elements.....	94
PRECEDENCE_RULE.....	94
PRECEDENCE_RULES.....	95
Profiles.xml elements.....	96
PROFILES.....	96
Project.xml elements.....	97
DIMENSION_INPUTS.....	97
INPUT.....	98
PROJECT.....	99
RECORD_INPUTS.....	99
Prop_refs.xml elements.....	100
PROP_REF.....	100
PROP_REFs.....	101
Record_filter.xml elements.....	102
RECORD_FILTER.....	102
Record_id_prop.xml elements.....	103
RECORD_ID_PROP.....	103
Record_sort_config.xml elements.....	104
RECORD_SORT.....	104
RECORD_SORT_CONFIG.....	105
Record_spec.xml element.....	106
RECORD_SPEC.....	106
Recsearch_config.xml elements.....	107
RECSEARCH_CONFIG.....	107
Recsearch_indexes.xml elements.....	109
RECSEARCH_INDEX.....	109
RECSEARCH_INDEXES.....	110

Refinement_config.xml elements.....	112
CLUSTERS.....	112
DYNAMIC_RANKING.....	114
REFINEMENTS.....	115
REFINEMENTS_CONFIG.....	116
STATS.....	117
Relrank_strategies.xml elements.....	118
RELRANK_APPROXPHRASE.....	119
RELRANK_EXACT.....	119
RELRANK_FIELD.....	120
RELRANK_FIRST.....	120
RELRANK_FREQ.....	121
RELRANK_GLOM.....	121
RELRANK_INTERP.....	122
RELRANK_MAXFIELD.....	122
RELRANK_MODULE.....	123
RELRANK_NTERMS.....	124
RELRANK_NUMFIELDS.....	124
RELRANK_PHRASE.....	125
RELRANK_PROXIMITY.....	126
RELRANK_SPELL.....	126
RELRANK_STATIC.....	127
RELRANK_STRATEGIES.....	127
RELRANK_STRATEGY.....	128
RELRANK_WFREQ.....	130
Render_config.xml elements.....	131
RENDER.....	131
RENDER_CONFIG.....	132
Rollups.xml elements.....	133
ROLLUP.....	133
ROLLUPS.....	133
Search_chars.xml elements.....	134
SEARCH_CHAR.....	134
SEARCH_CHARS.....	135
Searchindex.xml elements.....	135
POSITIONAL_INDEX.....	136
SEARCH_INDEX.....	136
WILDCARD_INDEX.....	137
Search_interface.xml elements.....	138
AUTO_SUGGEST.....	139
DID_YOU_MEAN.....	139
MEMBER_NAME.....	140
PARTIAL_MATCH.....	140
SEARCH_CORRECTION_PARAMETERS.....	141
SEARCH_INTERFACE.....	142
Spell_config.xml elements.....	144
ASPELL.....	144
DICT_PER_LANGUAGE.....	145
ESPELL.....	146
FIRST_DICT.....	147
SPELL_CONFIG.....	148
SPELL_ENGINE.....	149
UNION_DICTS.....	150
Stemming.xml elements.....	151
STEM_CS.....	152
STEM_DA.....	152
STEM_DE.....	152
STEM_EL.....	153
STEM_EN_UK.....	153
STEM_EN_US.....	153
STEM_ES.....	154
STEM_FR.....	154
STEM_HU.....	155
STEM_IT.....	155

STEM_JP.....	156
STEM_KO.....	157
STEM_NL.....	158
STEM_PL.....	158
STEM_PT.....	159
STEM_XX.....	159
STEM_ZH_CN.....	159
STEM_ZH_TW.....	160
Stop_words.xml elements.....	161
STOP_WORD.....	161
STOP_WORDS.....	162
Studio_project.esp elements.....	162
PROJECT_FILE.....	163
PROJECT_MANAGER_CONFIG.....	164
PROJECT_PIPELINE.....	164
STUDIO_PROJECT.....	165
Thesaurus.xml elements.....	166
THESAURUS.....	167
THESAURUS_ENTRY.....	167
THESAURUS_ENTRY_ONEWAY.....	168
THESAURUS_FORM.....	169
THESAURUS_FORM_FROM.....	169
THESAURUS_FORM_TO.....	170

Copyright and disclaimer

Copyright © 2003, 2013, Oracle and/or its affiliates. All rights reserved.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

This software or hardware and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

Preface

The Oracle Endeca Commerce solution enables your company to deliver a personalized, consistent customer buying experience across all channels — online, in-store, mobile, or social. Whenever and wherever customers engage with your business, the Oracle Endeca Commerce solution delivers, analyzes, and targets just the right content to just the right customer to encourage clicks and drive business results.

Oracle Endeca Commerce is the most effective way for your customers to dynamically explore your storefront and find relevant and desired items quickly. An industry-leading faceted search and Guided Navigation solution, Oracle Endeca Commerce enables businesses to help guide and influence customers in each step of their search experience. At the core of Oracle Endeca Commerce is the MDEX Engine™, a hybrid search-analytical database specifically designed for high-performance exploration and discovery. The Endeca Content Acquisition System provides a set of extensible mechanisms to bring both structured data and unstructured content into the MDEX Engine from a variety of source systems. Endeca Assembler dynamically assembles content from any resource and seamlessly combines it with results from the MDEX Engine.

Oracle Endeca Experience Manager is a single, flexible solution that enables you to create, deliver, and manage content-rich, cross-channel customer experiences. It also enables non-technical business users to deliver targeted, user-centric online experiences in a scalable way — creating always-relevant customer interactions that increase conversion rates and accelerate cross-channel sales. Non-technical users can control how, where, when, and what type of content is presented in response to any search, category selection, or facet refinement.

These components — along with additional modules for SEO, Social, and Mobile channel support — make up the core of Oracle Endeca Experience Manager, a customer experience management platform focused on delivering the most relevant, targeted, and optimized experience for every customer, at every step, across all customer touch points.

About this guide

This reference provides descriptions of the XML elements in Endeca project files, including the XML elements used to build components for a Forge pipeline.

It assumes that you are familiar with Endeca Developer Studio, with the concepts of the Endeca Information Transformation Layer, and with the configuration of the features of the Endeca MDEX Engine (such as search interfaces and dimensions). The general structure of the reference is based on the various XML files that constitute an Endeca project.

Who should use this guide

This guide is intended for application developers who are building Endeca applications. In particular, it is intended as a reference for developers who must work with the XML files that define an application.

Conventions used in this guide

This guide uses the following typographical conventions:

Code examples, inline references to code elements, file names, and user input are set in monospace font. In the case of long lines of code, or when inline monospace text occurs at the end of a line, the following symbol is used to show that the content continues on to the next line: `~`

When copying and pasting such examples, ensure that any occurrences of the symbol and the corresponding line break are deleted and any remaining space is closed up.

Contacting Oracle Support

Oracle Support provides registered users with important information regarding Oracle Endeca software, implementation questions, product and solution help, as well as overall news and updates.

You can contact Oracle Support through Oracle's Support portal, My Oracle Support at <https://support.oracle.com>.

Chapter 1

Endeca XML Reference

This reference describes the XML elements contained in the .xml files for an Endeca project.

Welcome

This reference describes the XML elements in Endeca project files. The reference documents each element's DTD, attributes, sub-elements, and provide an example of its usage.

When you create an Endeca project using Developer Studio, the application creates the .xml files for you. As you modify your project, Developer Studio and Oracle Endeca Workbench write your changes to the .xml files. This reference explains how to configure XML elements if you choose to modify the .xml files directly.

Customers should use Developer Studio or Oracle Endeca Workbench to configure a project and only modify the XML directly when required in unusual exceptions.

Analytics_config.xml elements

The Analytics_config.xml file is obsolete.

Common.dtd elements

Common.dtd defines common elements that are available for use in multiple Endeca XML files.

COMMENT

The COMMENT element associates a comment with a pipeline component and preserves the comment when the file is rewritten. This element provides an alternative to using inline XML comments of the form <!-- ... -->.

DTD

```
<!ELEMENT COMMENT (#PCDATA)>
```

Attributes

The COMMENT element has no attributes.

Sub-elements

The COMMENT element has no sub-elements.

Example

This example includes an informational comment.

```
<RECORD_ADAPTER URL=".../incoming/wine_data.txt" NAME="LoadMainData" FORMAT="DELIMITED"
DIRECTION="INPUT" FRC_PVAL_IDX="TRUE" COL_DELIMITER="|" ROW_DELIMITER="|\n"
FILTER_EMPTY_PROPS="TRUE">
  <COMMENT>This is the primary record adapter in the pipeline.</COMMENT>
</RECORD_ADAPTER>
```

compression

The compression entity controls the level of data compression. The entity declares a shortcut for the enumeration of possible COMPRESSION_LEVEL values. In the DTD, this entity is declared as % compression; however, in XML files, this entity is expanded to its full form as an attribute value COMPRESSION_LEVEL="...".

The default compression level for this attribute is 0 (no compression). The value -1 for this attribute has been deprecated. Values 1-9 indicate increasing levels of compression.



Note: Disregard parameter entities that appear in Common.dtd. They are set by the system and their values should not be modified.

DTD

```
<!ENTITY % compression "COMPRESSION_LEVEL (-1 | 0 | 1 | 2 | 3
| 4 | 5 | 6 | 7 | 8 | 9) #IMPLIED">
```

Example

This example shows an Indexer Adapter writing compressed records.

```
<INDEXER_ADAPTER COMPRESSION_LEVEL="7" FILTER_UNKNOWN_PROPS="TRUE"
  FRC_PVAL_IDX="TRUE" MULTI_PROP_NAME=""
  NAME="IndexerAdapter" OUTPUT_DIMENSION_FORMAT="XML"
  OUTPUT_PREFIX="wine" OUTPUT_RECORD_FORMAT="BINARY"
  OUTPUT_URL=".../partition0/forge_output/">
<RECORD_SOURCE>PropDimMapper</RECORD_SOURCE>
<DIMENSION_SOURCE>DimensionServer</DIMENSION_SOURCE>
<ROLLOVER CUTOFF="2000000000" NAME="RECORD"
  NUM_IDX="1" PROP_NAME="" PROP_TYPE="ALPHA"
  REMOVE_PROP="FALSE" ROLL_URL="">
```

```
TYPE="SIZE" VALIDATE="FALSE" />
</INDEXER_ADAPTER>
```

CONFIG

The CONFIG element provides generic configuration information as name/value pairs.

When used within a RECORD_JOIN element, CONFIG provides flags to adjust the behavior of join operations. The NAME attribute specifies the type of configuration flag, and the VALUE attribute either enables or disables the flag. For more information about joining source data, see the Endeca Developer Studio Help.

DTD

```
<!ELEMENT CONFIG EMPTY>
<!ATTLIST CONFIG
  NAME   CDATA  #REQUIRED
  VALUE  CDATA  #REQUIRED
>
```

Attributes

The following sections describe the CONFIG element's attributes.

NAME

Provides the name of a configuration option. There are three valid NAME values:

- MULTI_SUB_RECORDS Valid only for left joins when there are multiple values for a given key dimension. If the record from the Left source has multiple values for a key dimension, the values are to be OR'd (creating multiple record keys). For a record index with a single key dimension this means that each value of that key dimension is an independent record key.
- TRACK_PROP_SOURCE If this attribute is TRUE, a new property is added to the joined record that tracks the record source from which the property value originated. The value of the new property is a combination of the record source name, the property name, and property value. The default value of TRACK_PROP_SOURCE is FALSE.
- UNIQUE_RECORD_PROPS If this attribute is TRUE, duplicate property values (same name, value and children) are not added when records are combined. The property values of the new record are unique. The default value of UNIQUE_RECORD_PROPS is FALSE. See "Joining Source Data" in the Developer Studio help for more details about each NAME value.

VALUE

Provides a value that enables or disables the NAME configuration option. The valid values are TRUE or FALSE.

Sub-elements

The CONFIG element has no sub-elements.

Example

In this example, several name/value pairs are established as part of join processing.

```
<RECORD_JOIN JOIN_TYPE="OUTER_JOIN">
  <CONFIG NAME="MULTI_SUB_RECORDS" VALUE="FALSE" />
  <CONFIG NAME="TRACK_PROP_SOURCE" VALUE="FALSE" />
  <CONFIG NAME="UNIQUE_RECORD_PROPS" VALUE="FALSE" />
```

```
<JOIN_ENTRY>
  <RECORD_SOURCE>c1</RECORD_SOURCE>
  <KEY_DIMENSION TYPE="PROPERTY_VALUE" ID="record_id"/>
</JOIN_ENTRY>
<JOIN_ENTRY>
  <RECORD_SOURCE>c2</RECORD_SOURCE>
  <KEY_DIMENSION TYPE="PROPERTY_VALUE" ID="id"/>
</JOIN_ENTRY>
</RECORD_JOIN>
```

DIMENSION_ID

The DIMENSION_ID element specifies the ID number of a dimension.

DTD

```
<!ELEMENT DIMENSION_ID EMPTY>
<!ATTLIST DIMENSION_ID
  ID      CDATA      #REQUIRED
>
```

Attributes

The DIMENSION_ID element has no attributes.

Sub-elements

The DIMENSION_ID element has no sub-elements.

Example

In this example, a DIMENSION_REF element uses a DIMENSION_ID element to identify the dimension in question.

```
<DIMENSION_REF TYPE="SECONDARY" DIM_SEARCH_HIERARCHY="FALSE"
RECORD_SEARCH_HIERARCHY="FALSE">
  <DIMENSION_ID ID="12" />
</DIMENSION_REF>
```

DIMNAME

The DIMNAME element specifies the name of a dimension. This element provides an alternative to identifying a dimension by its ID with DIMENSION_ID.

DTD

```
<!ELEMENT DIMNAME (#PCDATA)>
```

Attributes

The DIMNAME element has no attributes.

Sub-elements

The DIMNAME element has no sub-elements.

Example

This example creates a dimension group with three dimensions identified by their DIMNAME element.

```
<DIMENSION_GROUP NAME="Features">
  <DIMNAME>Number of speakers</DIMNAME>
  <DIMNAME>Horizontal resolution</DIMNAME>
  <DIMNAME>Vertical resolution</DIMNAME>
</DIMENSION_GROUP>
```

DVAL_ID

The DVAL_ID element specifies a dimension value ID.

DTD

```
<!ELEMENT DVAL_ID EMPTY>
<!ATTLIST DVAL_ID
  DIMENSION_ID   CDATA    #IMPLIED
  ID             CDATA    #REQUIRED
  >
```

Attributes

The following sections describe the DVAL_ID attributes.

DIMENSION_ID

Specifies the dimension ID. This provides a way of specifying the DIMENSION_ID as an attribute of DVAL_ID.

ID

Specifies the dimension value ID.

Sub-elements

The DVAL_ID element has no sub-elements.

Example

In this example, a DVAL_ID is associated with a DVAL_REF.

```
<DIMENSION_REF DIM_SEARCH_HIERARCHY="FALSE" HIDDEN="TRUE"
  RECORD_SEARCH_HIERARCHY="FALSE" TYPE="PRIMARY">
  <DIMENSION_ID ID="1"/>
  </DIMENSION_REF>
  <DVAL_REF RANK="75">
    <DVAL_ID ID="2116"/>
  </DVAL_REF>
  . . .
```

DVAL_PATH

The DVAL_PATH element provides an alternative way to specify a dimension value. It specifies the names of all of the dimension values in a path, starting with the root of the dimension and including the name of the target dimension value itself.

DTD

```
<!ELEMENT DVAL_PATH EMPTY>
<!ATTLIST DVAL_PATH
  DIMENSION_NAME   CDATA      #IMPLIED
  PATH             CDATA      #REQUIRED
>
```

Attributes

The following sections describe the DVAL_PATH attributes.

DIMENSION_NAME

The name of the target dimension value.

PATH

The full path to the target dimension value, starting with the root of the dimension. Nodes in the path are separated by a forward slash (/). If the target dval contains a forward slash, you have to add a back slash to the path (to escape the character) before adding the forward slash separator. See the example below.

Sub-elements

The DVAL_PATH element has no sub-elements.

Example

This example shows two DVAL_PATH elements declared in a precedence_rules.xml file. The first DVAL_PATH represents an "Endeca" DIMENSION_NODE followed by a nested "Endeca-Cat". Neither of these two individual dimension values has a forward slash as part of their SYN PCDATA and consequently, the path can be separated with the forward slash. The second DVAL_PATH entry represents an "A-root" DIMENSION_NODE followed by a nested "Value/X". Because "Value/X" contains a forward slash, the PATH value requires "\" before "/X".

```
<PRECEDENCE_RULE TYPE="STANDARD">
  <DVAL_PATH PATH="Endeca/Endeca-Cat" />
  <DVAL_PATH DIMENSION_NAME="A" PATH="A-root/Value\X" />
</PRECEDENCE_RULE>
```

KEY_DIMENSION

The KEY_DIMENSION element determines how records are compared by the join implementation. They are used to create a record key for a record from the specified source.

DTD

```
<!ELEMENT KEY_DIMENSION EMPTY>
<!ATTLIST KEY_DIMENSION
  TYPE      ( PVAL | DVAL | PROPERTY_VALUE )      #REQUIRED
  ID        CDATA                                #REQUIRED
  MIN_VALS CDATA                                " 0 "
```

Attributes

The following section describes KEY_DIMENSION element's attributes.

TYPE

Select PVAL for property values or DVAL for dimension values. PROPERTY_VALUE has been deprecated. Comparison of a value for a key dimension of type PVAL implies comparison of the value of the properties (the name of the property values are not considered). For key dimensions of type DVAL, the name of the dimension values are compared (neither the dimension name nor the dimension ID influence the comparison).

ID

The ID attribute is the property name (when TYPE=PVAL) or dimension ID (when TYPE=DVAL) of the index key.

MIN_VALS

Specifies the minimum number of values.

Sub-elements

The KEY_DIMENSION element has no sub-elements.

Example

The following example is taken from a typical record assembler.

```
<RECORD_JOIN JOIN_TYPE="LEFT_JOIN">
  <JOIN_ENTRY>
    <RECORD_SOURCE>rs-1</RECORD_SOURCE>
    <KEY_DIMENSION TYPE="PVAL" ID="sid"/>
  </JOIN_ENTRY>
  ...

```

LOG

The LOG element creates a log file for Pipeline.epx components that write to a log. For example the DVAL MATCH expression often writes to a log during processing. This logging information is not the same as the output messages from Forge about record processing.



Note: The LOG element has been deprecated. See the *Endeca Log Server and Report Generator Guide* for details about how to implement logging in your Endeca application.

DTD

```
<!ELEMENT LOG EMPTY>
<!ATTLIST LOG
  NAME   CDATA          #REQUIRED
  TYPE   (SIMPLE | UNIQUE) #REQUIRED
  URL    CDATA          #IMPLIED
  FILE   CDATA          #IMPLIED
  %compression;
>
```

Attributes

The following sections describe the LOG element's attributes.

NAME

The name of the log file.

TYPE

The type of the log file. SIMPLE indicates that the individual messages should be logged consecutively as they come in. UNIQUE indicates that each message should be made unique by removing duplicates.

URL

Provides a path to the log file.

FILE

FILE has been deprecated; use URL instead.

COMPRESSION_LEVEL

Controls the level of data compression when writing log files. The default compression level for this attribute is 0 (no compression). The value "-1" for this attribute has been deprecated. Values 1-9 indicate increasing levels of compression.

Sub-elements

The LOG element has no sub-elements.

Example

This example establishes a log pipeline.

```
<LOG URL=".../.../logs/pipeline.log" NAME="LogFile" TYPE="UNIQUE" />
```

PHRASE

The PHRASE element specifies a phrase entry for use with the Automatic Phrasing feature. The MDEX Engine treats each phrase entry as a search phrase rather than as separate search terms.

When automatic phrasing is implemented in an application, the MDEX Engine can suggest automatically phrased queries to a user or process automatically phrased queries by default. For example, if a user enters the search terms [Kenneth Cole blue jeans], and those terms are specified as in the example below, the application can return Did you mean ["Kenneth Cole" "blue jeans"]? Or depending on how automatic phrasing is implemented, the application may process the query as ["Kenneth Cole" "blue jeans"]. For details about automatic phrasing, see the *Endeca Advanced Development Guide*.

DTD

```
<!ELEMENT PHRASE (#PCDATA) >
```

Attributes

The PHRASE element has no attributes.

Sub-elements

The PHRASE element has no sub-elements.

Example

The example below adds two phrases to the phrase dictionary.

```
<PHRASE_IMPORT>
  <PHRASE>Kenneth Cole</PHRASE>
  <PHRASE>blue jeans</PHRASE>
</PHRASE_IMPORT>
```

PROFILE

The PROFILE element specifies a user type or user group.

Profiles are used as a type of dynamic business rule trigger. See "Implementing User Profiles" in the *Endeca MDEX Engine Advanced Development Guide* for more information.

DTD

```
<!ELEMENT PROFILE (#PCDATA)>
```

Attributes

The PROFILE element has no attributes.

Sub-elements

The PROFILE element has no sub-elements.

Example

This example identifies a user type named premium_subscriber.

```
<PROFILE>premium_subscriber</PROFILE>
```

PROP

The PROP element represents a property.

DTD

```
<!ELEMENT PROP (PVAL)>
<!ATTLIST PROP
  NAME      CDATA      #REQUIRED
  UPDATE    (A | C | D) #IMPLIED
>
```

Attributes

The following sections describe the PROP element's attributes.

NAME

Identifies the name of the property.

Sub-elements

The PROP element has no sub-elements.

Example

This example shows a property name.

```
<RECORD>
  <PROP NAME="Endeca.Title">
    <PVAL>The Simpsons Archive</PVAL>
  </PROP>
  ...

```

PROPNAMEx

The PROPNAMEx element represents a property.

DTD

```
<!ELEMENT PROPNAMEx (#PCDATA)>
```

Attributes

The PROPNAMEx element has no attributes.

Sub-elements

The PROPNAMEx element has no sub-elements.

Example

This example identifies records to update by the Number property.

```
<RECORD_SPEC>
  <PROPNAMEx>Number</PROPNAMEx>
</RECORD_SPEC>
```

PVAL

The PVAL element represents a property value.

DTD

```
<!ELEMENT PVAL (#PCDATA)>
```

Attributes

The PVAL element has no attributes.

Sub-elements

The PVAL element has no sub-elements.

Example

This example shows a property value.

```
<PROP NAME="Endeca.Title">
  <PVAL>The Simpsons Archive</PVAL>
</PROP>
```

RECORD_GROUP

The RECORD_GROUP element provides property and dimension keys for record grouping.

DTD

```
<ELEMENT RECORD_GROUP (KEY_DIMENSION+)>
```

Attributes

The RECORD_GROUP element has no attributes.

Sub-elements

KEY_DIMENSION: Determines how records are to be compared by the join implementation.

RECORD_ID

The RECORD_ID element specifies the ID number for a record.

DTD

```
<!ELEMENT RECORD_ID EMPTY>
<!ATTLIST RECORD_ID
      ID      CDATA      #REQUIRED
>
```

Attributes

The following section describes the RECORD_ID element's attribute.

ID

The ID attribute provides the ID number of a records.

Sub-elements

The RECORD_ID element has no sub-elements.

RECORD_INDEX

The RECORD_INDEX element specifies a common key used to identify records for record retrieval, join operations, sort validation, and logging.

DTD

```
<!ELEMENT RECORD_INDEX (KEY_DIMENSION+)>
<!ATTLIST RECORD_INDEX
      UNIQUE      (TRUE | FALSE)      #IMPLIED
>
```

Attributes

The following section describes the RECORD_INDEX element's attribute.

UNIQUE

Specifies whether the property or dimension key is unique or not. When set to TRUE, Forge checks for duplicated keys and warns if they exist. That is the attribute's behavior when it is nested in any pipeline component except a record cache. This attribute behaves differently when it is nested within a parent RECORD_CACHE element. When set to TRUE, Forge discards any records with duplicate keys and logs a warning that specifies the number of records discarded.

Sub-elements

The following table provides a brief overview of the RECORD_INDEX sub-elements. Click a sub-element name to view complete details.

Example

The example below specifies that the source contains records sorted by BID and can look up records on the same.

```
<RECORD_ADAPTER ...>
  <RECORD_INDEX>
    <KEY_DIMENSION ID="BID" TYPE="PVAL" />
  </RECORD_INDEX>
</RECORD_ADAPTER>
```

Derived_props.xml elements

The Derived_props.xml file specifies derived properties for aggregated records in your pipeline.

You can specify any number of derived properties in the DERIVED_PROPS element. See "Using Derived Properties" in the *Endeca Basic Development Guide* for more information.

DERIVED_PROP

A DERIVED_PROP element applies a function to property or dimension values from the member records of an aggregated record.

The resultant derived property is assigned to the aggregated record, giving you more control over representative values as well as over sort. See "Using Derived Properties" in the *Endeca MDEX Engine Basic Development Guide* for more information.

DTD

```
<!ELEMENT DERIVED_PROP EMPTY>
<!ATTLIST DERIVED_PROP
  NAME          CDATA          #REQUIRED
  FCN           (MIN | MAX | SUM | AVG) #REQUIRED
  DERIVE_FROM   CDATA          #REQUIRED
>
```

Attributes

The following section describes DERIVED_PROP element's attributes.

NAME

A unique name for this derived property.

FCN

The function you want performed on the specified dimension or property to generate the derived property. One of the following values: MIN, MAX, AVG, or SUM.

DERIVE_FROM

The name of the property or dimension from which the derived property is drawn.

Sub-elements

DERIVED_PROP contains no sub-elements.

Example

In this example, a derived property called `priceDerived` is generated.

```
<DERIVED_PROP FCN="SUM" NAME="priceDerived"
  DERIVE_FROM="P_PriceStr" />
```

DERIVED_PROPS

A DERIVED_PROPS element contains any number of derived properties indicated by DERIVED_PROP elements.

DTD

```
<!ELEMENT DERIVED_PROPS (COMMENT?, DERIVED_PROP*)>
```

Attributes

The DERIVED_PROPS element has no attributes.

Sub-elements

The following table provides a brief overview of the DERIVED_PROPS sub-elements.

Sub-element	Brief description
COMMENT	Associates a comment with a parent element and preserves the comment when the file is rewritten. This element provides an alternative to using inline XML comments of the form <!-- ... -->.
DERIVED_PROP	Applies a function to property or dimension values from the member records of an aggregated record.

Example

This example generates two derived properties called `maxPrice` and `minPrice`.

```
<DERIVED_PROPS>
  <DERIVED_PROP FCN="MAX" NAME="maxPrice" DERIVE_FROM="p_Price" />
  <DERIVED_PROP FCN="MIN" NAME="minPrice" DERIVE_FROM="p_Price" />
</DERIVED_PROPS>
```

Dimensions.xml elements

The Dimensions.xml file defines the hierarchical structure of your source data using dimensions and dimension values.

These dimensions and dimension values are what Oracle Endeca Commerce uses to classify your source data for navigation. Dimensions.xml can describe dimensions created by Developer Studio (internal, autogen or property mapped dimensions) or dimensions created using a third-party tool (external dimensions).

If it is convenient for organizational purposes, you can include multiple Dimensions.xml files in your pipeline. See the *Endeca MDEX Engine Basic Development Guide* for more detailed conceptual information.

BOUND

A BOUND element specifies the boundary constraints for a range of dimension values. The attributes of a BOUND element provide data type, value, and inclusion rules for the range value. Use BOUND as a sub-element of LBOUND and UBOUND.

DTD

```
<!ELEMENT BOUND EMPTY>
<!ATTLIST BOUND
  TYPE      (STRING | INTEGER | FLOAT | CURRENCY | DATE) #REQUIRED
  VALUE     CDATA          #REQUIRED
  CLOSURE   (OPEN | CLOSED) #REQUIRED
>
```

Attributes

The following sections describe the BOUND element's attributes.

TYPE

The data type of the BOUND value. Must be set equal to one of the following: STRING, INTEGER, FLOAT, or CURRENCY. (DATE is not supported.)

VALUE

The desired value for the boundary. This value must correspond to the data type specified in TYPE.

CLOSURE

Closure is a mathematical term that specifies whether the VALUE is included or excluded from the boundary range. CLOSED means the value is included in the range. OPEN means numbers up to or down to the VALUE are included, but the VALUE itself is not included. Must be set equal to OPEN or CLOSED.

Sub-elements

The BOUND element has no sub-elements.

Example

This example shows two BOUND elements that define a range of 0 to 10 for the dimension value 0 to 10. The values 0 and 10 are included in the range.

```
<DIMENSION_NODE>
  <DVAL TYPE="RANGE">
    <DVAL_ID ID="21" />
    <SYN SEARCH="FALSE" DISPLAY="TRUE" CLASSIFY="FALSE">0 to 10</SYN>
    <LBOUND>
      <BOUND TYPE="INTEGER" VALUE="0" CLOSURE="CLOSED" />
    </LBOUND>
    <UBOUND>
      <BOUND TYPE="INTEGER" VALUE="10" CLOSURE="CLOSED" />
    </UBOUND>
```

```
</DVAL>
</DIMENSION_NODE>
```

DIMENSION

A DIMENSION element defines a single dimension for a navigation hierarchy. You can create dimensions using Developer Studio which are called internal dimensions. You can create dimensions based on external taxonomies, which are called external dimensions. The MDEX Engine requires one primary dimension, typically named Endeca. The dimensions that follow are secondary and typically reflect the logical categories of your source data.

DTD

```
<!ELEMENT DIMENSION (DIMENSION_ID, DIMENSION_NODE) >
<!ATTLIST DIMENSION
  NAME      CDATA      #IMPLIED
  SRC_TYPE  (INTERNAL | PROPMAPPER | AUTOGEN | EXTERNAL) #IMPLIED
  SRC_FILE  CDATA      #IMPLIED
>
```

Attributes

The following section describes the DIMENSION element's attribute.

NAME

Specifies a unique name for the dimension.

SRC_TYPE

Specifies how the dimension was created and whether the dimension can be edited using Developer Studio. This attribute is for internal use by Oracle Endeca Guided Search and should not be modified. The following values are valid:

- INTERNAL Indicates a pipeline developer manually created the dimension using Developer Studio.
- PROPMAPPER Indicates Developer Studio created the dimension during property mapping. Developer Studio cannot edit the dimension.
- AUTOGEN Indicates Developer Studio automatically generated the dimension. Developer Studio cannot edit the dimension.
- EXTERNAL Indicates a third-party tool created the dimension. Developer Studio cannot edit the dimension.

SRC_FILE

Specifies the source file from which the dimension originated, if applicable. This attribute is for internal use by Oracle Endeca Guided Search and should not be modified.

Sub-elements

The following table provides a brief overview of the DIMENSION sub-elements. Click a sub-element name to view complete sub-element details.

Sub-element	Brief description
DIMENSION_ID	Specifies the ID number of a dimension.
DIMENSION_NODE	Provides additional information about the DIMENSION element and allows you to nest additional DIMENSION_NODE

Sub-element	Brief description
	sub-elements to create a deeper dimension hierarchy within DIMENSION.

Example

This example shows a dimension named Year.

```
<DIMENSION NAME="Year" SRC_TYPE="INTERNAL">
  <DIMENSION_ID ID="2" />
  <DIMENSION_NODE>
    <DVAL TYPE="EXACT">
      <DVAL_ID ID="2" />
      <SYN SEARCH="FALSE" DISPLAY="TRUE" CLASSIFY="FALSE">Year</SYN>
    </DVAL>
  </DIMENSION_NODE>
</DIMENSION>
```

DIMENSIONS

The DIMENSIONS element is the root element of the Dimension.xml file. It serves as a container for any number of DIMENSION elements which organize your navigation hierarchy. DIMENSIONS may also include the number of dimension values in the file.

DTD

```
<!ELEMENT DIMENSIONS (NUM_DVALS?, DIMENSION*)>
<!ATTLIST DIMENSIONS
  VERSION      CDATA      #IMPLIED
>
```

Attributes

The following sections describe the DIMENSIONS element's attributes.

VERSION

This attribute is not currently used.

Sub-elements

The following table provides a brief overview of the DIMENSIONS sub-elements. Click a sub-element name to view complete sub-element details.

Sub-element	Brief description
NUM_DVALS	Specifies the total number of DVAL sub-elements after Forge processes your source data.
DIMENSION	Defines a single dimension for a navigation hierarchy.

Example

Defines a single dimension for a navigation hierarchy.

```
<DIMENSIONS VERSION="1.0.0">
    <DIMENSION NAME="Wine Type" SRC_TYPE="INTERNAL">
        ... (any number of DIMENSION elements may appear here)...
    </DIMENSION>
</DIMENSIONS>
```

DIMENSION_NODE

A DIMENSION_NODE element serves two functions: it provides additional information about the DIMENSION element, and it allows you to nest additional DIMENSION_NODE sub-elements to create a deeper dimension hierarchy within the parent DIMENSION.

DTD

```
<!ELEMENT DIMENSION_NODE (DVAL, DIMENSION_NODE*)>
```

Attributes

The DIMENSION_NODE element does not have any attributes.

Sub-elements

The following table provides a brief overview of the DIMENSION_NODE sub-elements. Click a sub-element name to view complete details.

Sub-elements	Brief description
DVAL	Contains an ID, one or more synonyms, and may contain boundary values for the DIMENSION.
DIMENSION_NODE	Provides additional information about the DIMENSION element and allows you to nest additional DIMENSION_NODE sub-elements to create a deeper dimension hierarchy within DIMENSION.

Example

This example shows two DIMENSION_NODE elements nested within the parent DIMENSION named Designation. It also shows how the two additional dimension nodes named Highly Recommended and Best Buy create a deeper hierarchy under Designation.

```
<DIMENSION NAME="Designation" SRC_TYPE="INTERNAL">
    <DIMENSION_ID ID="7"/>
    <DIMENSION_NODE>
        <DVAL TYPE="EXACT">
            <DVAL_ID ID="7"/>
            <SYN SEARCH="FALSE" DISPLAY="TRUE" CLASSIFY="FALSE">Designation</SYN>
        </DVAL>
        <DIMENSION_NODE>
            <DVAL TYPE="EXACT">
                <DVAL_ID ID="8029"/>
                <SYN SEARCH="FALSE" DISPLAY="TRUE" CLASSIFY="TRUE">Highly Recommended</SYN>
```

```

</DVAL>
</DIMENSION_NODE>
<DIMENSION_NODE>
<DVAL TYPE="EXACT">
  <DVAL_ID ID="8031"/>
  <SYN SEARCH="FALSE" DISPLAY="TRUE" CLASSIFY="TRUE">Best Buy</SYN>

</DVAL>
</DIMENSION_NODE>
</DIMENSION_NODE>
</DIMENSION>

```

DVAL

A DVAL element contains an ID, one or more synonyms, property matching instructions, and may contain boundary values for the DIMENSION.

DTD

```

<!ELEMENT DVAL (DVAL_ID, SYN+, LBOUND?, UBOUND?, PROP*)>
<!ATTLIST DVAL
  TYPE (EXACT | RANGE | LEVEL | SIFT | DVAL) #REQUIRED
>

```

Attributes

The following sections describe the DVAL element's attributes.

TYPE

The type attribute specifies how property values are matched to synonyms during classification. Any of the following values are acceptable:

- EXACT — Matches if the text within SYN is an exact match. For example, "Year" and "Year" are an exact match; however, "Year" and "YEAR" are not.
- RANGE — Matches if the property value falls within the specified range. See the BOUND element for more information about specifying a range of values.
- LEVEL — Matches different properties at different levels in the hierarchy. Note that LEVEL is no longer supported.
- SIFT — Matches if the property value falls within a sifted range several layers within a dimension hierarchy. Use the BOUND element to specify the range to match.
- DVAL — DVAL is deprecated. Use EXACT instead.

Sub-elements

The following table provides a brief overview of the DVAL sub-elements.

Sub-element	Brief description
DVAL_ID	Specifies the dimension value ID.
SYN	Specifies synonyms and processing settings for the particular DIMENSION value.
LBOUND	Specifies the lower boundary constraints for a range of dimension values.

Sub-element	Brief description
UBOUND	Specifies the upper boundary constraints for a range of dimension values.
PROP	Represents a property.

Example

This example defines a dimension value with the following characteristics:

- An ID of 30
- A displayable synonym of 91 to 100
- A range of 91 to 100

```
<DIMENSION_NODE>
  <DVAL TYPE="RANGE">
    <DVAL_ID ID="30"/>
    <SYN SEARCH="FALSE" DISPLAY="TRUE" CLASSIFY="FALSE">91 to 100</SYN>
    <LBOUND>
      <BOUND TYPE="INTEGER" VALUE="91" CLOSURE="CLOSED"/>
    </LBOUND>
    <UBOUND>
      <BOUND TYPE="INTEGER" VALUE="100" CLOSURE="CLOSED"/>
    </UBOUND>
  </DVAL>
</DIMENSION_NODE>
```

LBOUND

A LBOUND element specifies the lower boundary constraints for a range dimension value. Both LBOUND and UBOUND require the sub-element BOUND to provide data type, value, and inclusion rules for the range value.

DTD

```
<!ELEMENT LBOUND ( BOUND )>
```

Attributes

The LBOUND element does not have any attributes.

Sub-elements

The following table provides a brief overview of the LBOUND sub-elements.

Sub-element	Brief description
BOUND	Specifies the boundary constraints for a range dimension value.

Example

This example shows the LBOUND element defining a lower value of 0 in range of 0 to 10. The UBOUND element defines the upper range of 10. The values 0 and 10 are included in the range.

```
<DIMENSION_NODE>
  <DVAL TYPE="RANGE">
    <DVAL_ID ID="21"/>
```

```
<SYN SEARCH="FALSE" DISPLAY="TRUE" CLASSIFY="FALSE">0 to 10</SYN>
  <LBOUND>
    <BOUND TYPE="INTEGER" VALUE="0" CLOSURE="CLOSED" />
  </LBOUND>
  <UBOUND>
    <BOUND TYPE="INTEGER" VALUE="10" CLOSURE="CLOSED" />
  </UBOUND>
</DVAL>
</DIMENSION_NODE>
```

NUM_DVALS

A NUM_DVALS element specifies the total number of DVAL sub-elements after Forge processes your source data. This element does not appear in the dimension.xml files used as input to Forge. This is not an element that you should add to your dimension.xml input files. Forge calculates this value and writes it to dimensions.xml. Dgidx uses this value; you should not edit it.

DTD

```
<!ELEMENT NUM_DVALS (#PCDATA)>
```

Attributes

The NUM_DVALS element does not have any attributes.

Sub-elements

The NUM_DVALS element does not have any sub-elements.

Example

This example shows the number of DVALS that appear after Forge processes the source data.

```
<DIMENSIONS VERSION="1.0.0">
  <NUM_DVALS>8067</NUM_DVALS>
```

SYN

A SYN element specifies synonyms and processing settings for a particular DIMENSION value.

Synonyms provide alternative ways of describing and consequently, searching a particular dimension. If you created your dimension elements within the Endeca Developer Studio, Developer Studio generates XML with the same name for SYN and DIMENSION value.

DTD

```
<!ELEMENT SYN (#PCDATA)>
<!ATTLIST SYN
  DISPLAY      ( TRUE  |  FALSE )    #REQUIRED
  SEARCH      ( TRUE  |  FALSE )    #REQUIRED
  CLASSIFY    ( TRUE  |  FALSE )    #REQUIRED
>
```

Attributes

The following sections describe the SYN element's attributes.

DISPLAY

Specifies which synonym is displayed to the user. TRUE indicates the synonym is displayed. FALSE indicates it is not.

SEARCH

Specifies whether Dgidx indexes the dimension. TRUE indicates that the value is indexed during property-to-dimension mapping. FALSE indicates it is not.

CLASSIFY

Controls property-to-dimension mapping. TRUE indicates that the value is used during property-to-dimension mapping. FALSE indicates the value is not.

Sub-elements

The SYN element does not have any sub-elements.

Example

This example shows SYN elements where US, USA, and United States are synonyms but only "United States" displays for dimension searches using "US" or "USA".

```
<DIMENSION NAME="Country" SRC_TYPE="INTERNAL">
  <DIMENSION_ID ID="2"/>
  <DIMENSION_NODE>
    <DVAL TYPE="EXACT">
      <DVAL_ID ID="2"/>
      <SYN SEARCH="TRUE" DISPLAY="FALSE" CLASSIFY="TRUE">USA</SYN>
      <SYN SEARCH="TRUE" DISPLAY="FALSE" CLASSIFY="FALSE">US</SYN>
      <SYN SEARCH="FALSE" DISPLAY="TRUE" CLASSIFY="TRUE">United
      States</SYN>
    </DVAL>
  </DIMENSION_NODE>
</DIMENSION>
```

UBOUND

A UBOUND element specifies the upper boundary constraints for a range of dimension values. Both UBOUND and LBOUND require the sub-element BOUND to provide data type, value, and inclusion rules for the range value.

DTD

```
<!ELEMENT UBOUND ( BOUND )>
```

Attributes

The UBOUND element does not have any attributes.

Sub-elements

The following table provides a brief overview of the UBOUND sub-elements.

Sub-element	Brief description
BOUND	Specifies the boundary constraints for a range dimension value.

Example

This example shows the LBOUND element defining a lower value of 0 in range of 0 to 10. The UBOUND element defines the upper range of 10. The values 0 and 10 are included in the range.

```
<DIMENSION_NODE>
  <DVAL TYPE="RANGE">
    <DVAL_ID ID="21"/>
    <SYN SEARCH="FALSE" DISPLAY="TRUE" CLASSIFY="FALSE">0 to 10</SYN>
    <LBOUND>
      <BOUND TYPE="INTEGER" VALUE="0" CLOSURE="CLOSED"/>
    </LBOUND>
    <UBOUND>
      <BOUND TYPE="INTEGER" VALUE="10" CLOSURE="CLOSED"/>
    </UBOUND>
  </DVAL>
</DIMENSION_NODE>
```

Dimension_groups.xml elements

The Dimension_groups.xml file allows you to organize dimensions into explicit groupings for presentation purposes.

Explicit dimension groups that you establish provide a way to impose relationships on dimensions and take precedence over implicit, system-generated dimension groups containing a single member each.

A dimension can only belong to one dimension group. For example, if a data set has ten dimensions and one explicit dimension group containing five dimensions has been created, then there are six dimension groups: one explicit group and five implicit ones.

DIMENSION_GROUP

The DIMENSION_GROUP element specifies that a group of dimensions should be returned together when sent back from the MDEX Engine.

The order of the dimension groups is determined by the highest ranked dimension within each group. To control the order in which dimensions are returned, you should use the DVAL_REF element to specify a RANK for the root dimension value of the dimension. That same rank determines how dimensions are ordered within a dimension group.

DTD

```
<!ELEMENT DIMENSION_GROUP (DIMNAME+)>
<!ATTLIST DIMENSION_GROUP
  NAME      CDATA      #REQUIRED
>
```

Attributes

The following section describes the DIMENSION_GROUP element's attribute.

NAME

A unique name for this dimension group.

Sub-elements

The following table provides a brief overview of the DIMENSION_GROUP sub-elements.

Sub-element	Brief description
DIMNAME	Specifies the name of a dimension. This element provides an alternative to identifying a dimension by its ID with DIMENSION_ID.

Example

This example shows dimension groups used in the wine reference implementation.

```
<DIMENSION_GROUPS>
  <DIMENSION_GROUP NAME="Characteristics">
    <DIMNAME>Body</DIMNAME>
  </DIMENSION_GROUP>
  <DIMENSION_GROUP NAME="Ratings">
    <DIMNAME>Drinkability</DIMNAME>
    <DIMNAME>Designation</DIMNAME>
    <DIMNAME>Score</DIMNAME>
  </DIMENSION_GROUP>
  <DIMENSION_GROUP NAME="Geographic Information">
    <DIMNAME>Appellations</DIMNAME>
    <DIMNAME>Region</DIMNAME>
    <DIMNAME>Winery</DIMNAME>
  </DIMENSION_GROUP>
</DIMENSION_GROUPS>
```

DIMENSION_GROUPS

A DIMENSION_GROUPS element contains any number of dimension groups indicated by DIMENSION_GROUP elements.

DTD

```
<!ELEMENT DIMENSION_GROUPS (COMMENT?, DIMENSION_GROUP*)>
```

Attributes

The DIMENSION_GROUPS element has no attributes.

Sub-elements

The following table provides a brief overview of the DIMENSION_GROUP sub-elements.

Sub-element	Brief description
COMMENT	Associates a comment with a parent element and preserves the comment when the file is rewritten. This element provides an alternative to using inline XML comments of the form <!-- ... -->.
DIMENSION_GROUP	Specifies that a group of dimensions should be returned together when sent back from the MDEX Engine.

Example

This example shows dimension groups used in the wine reference implementation.

```
<DIMENSION_GROUPS>
  <DIMENSION_GROUP NAME="Characteristics">
    <DIMNAME>Body</DIMNAME>
  </DIMENSION_GROUP>
  <DIMENSION_GROUP NAME="Ratings">
    <DIMNAME>Drinkability</DIMNAME>
    <DIMNAME>Designation</DIMNAME>
    <DIMNAME>Score</DIMNAME>
  </DIMENSION_GROUP>
  <DIMENSION_GROUP NAME="Geographic Information">
    <DIMNAME>Appellations</DIMNAME>
    <DIMNAME>Region</DIMNAME>
    <DIMNAME>Winery</DIMNAME>
  </DIMENSION_GROUP>
</DIMENSION_GROUPS>
```

Dimension_refs.xml elements

The Dimension_refs.xml file contains a DIMENSION_REF element for every dimension in your hierarchy.

The DIMENSION_REF allows you to specify whether a dimension is hidden in the application's user interface and how dimension values may be returned when more than one dimension value is selected from a dimension. DIMENSION_REF elements are grouped in the DIMENSION_REFS element.

DIMENSION_REF

The DIMENSION_REF element describes the various attributes of a dimension.

DTD

```
<!ELEMENT DIMENSION_REF EMPTY>
<!ATTLIST DIMENSION_REF
  NAME      CDATA          #REQUIRED
  TYPE      (PRIMARY | SECONDARY) #REQUIRED
  HIDDEN    (TRUE | FALSE)      "FALSE"
  MULTI     (OR | AND)        #IMPLIED
>
```

Attributes

The following sections describe the DIMENSION_REF element's attributes.

NAME

Specifies a unique name for the DIMENSION_REF.

TYPE

In pre-6.1 implementations, this attribute specified whether this dimension was a primary dimension or a secondary dimension. As of version 6.1, this distinction is now ignored and all dimensions are treated the same. That is, regardless of whether a dimension is configured as type PRIMARY or SECONDARY, the value is ignored by Dgidx and the MDEX Engine. However, because the TYPE

attribute is required by Developer Studio, it is recommended that you specify SECONDARY as the type for all dimensions.

HIDDEN

Specifies whether or not this dimension is shown in the navigation controls. The default value is FALSE.

MULTI

Allows the user to select more than one dimension value from a dimension. When set to OR, the MDEX Engine returns dimension values that match either search term. When set to AND, the MDEX Engine returns dimension values that match both search terms.

Sub-elements

DIMENSION_REF contains no sub-elements.

Example

This example shows a small number of dimensions in a pipeline that may appear in the application's navigation controls.

```
<DIMENSION_REFS>
  <DIMENSION_REF NAME="Camcorder Features" TYPE="SECONDARY" HIDDEN="FALSE" />
  <DIMENSION_REF NAME="Camcorder Formats" TYPE="SECONDARY" HIDDEN="FALSE" />
  <DIMENSION_REF NAME="Camcorder Size" TYPE="SECONDARY" HIDDEN="FALSE" />
  <DIMENSION_REF NAME="Camera Types" TYPE="SECONDARY" HIDDEN="FALSE" />
  ...Others deleted for simplicity...
</DIMENSION_REFS>
```

DIMENSION_REFS

A DIMENSION_REFS element contains any number of dimensions indicated by DIMENSION_REF elements.

DTD

```
<!ELEMENT DIMENSION_REFS (COMMENT?, DIMENSION_REF*)>
```

Attributes

The DIMENSION_REFS element has no attributes.

Sub-elements

The following table provides a brief overview of the DIMENSION_REFS sub-elements.

Sub-element	Brief description
COMMENT	Associates a comment with a parent element and preserves the comment when the file is rewritten. This element provides an alternative to using inline XML comments of the form <!-- ... -->.
DIMENSION_REFS	Describes the various attributes of a dimension.

Example

This example shows a small number of dimensions in a pipeline that may appear in the application's navigation controls.

```
<DIMENSION_REFS>
  <DIMENSION_REF NAME="Camcorder Features" TYPE="SECONDARY" HIDDEN="FALSE" />
  <DIMENSION_REF NAME="Camcorder Formats" TYPE="SECONDARY" HIDDEN="FALSE" />
  <DIMENSION_REF NAME="Camcorder Size" TYPE="SECONDARY" HIDDEN="FALSE" />
  <DIMENSION_REF NAME="Camera Types" TYPE="SECONDARY" HIDDEN="FALSE" />
  ...Others deleted for simplicity...
</DIMENSION_REFS>
```

Dimsearch_config.xml elements

The Dimsearch_config.xml file controls how dimension searches behave.

This file configures search matching, spelling correction, filtering, and relevance ranking for dimension search. These options are configured in the file's root element DIMSEARCH_CONFIG.

DIMSEARCH_CONFIG

A DIMSEARCH_CONFIG element sets up the configuration of dimensions for dimension searches. Dimension searches search against the text collection that consists of the names of all the dimension values in the data set.

DTD

```
<!ELEMENT DIMSEARCH_CONFIG (COMMENT?, PARTIAL_MATCH?, AUTO_SUGGEST?)>
<!ATTLIST DIMSEARCH_CONFIG
  FILTER_FOR_ANCESTORS      (TRUE | FALSE)      "FALSE"
  SEARCH_INERT_DVALS        (TRUE | FALSE)      "FALSE"
  RELRANK_STRATEGY          CDATA             #IMPLIED
  RETURN_RELRANK_SCORE      (TRUE | FALSE)      "FALSE"
  ENABLE_AUTO_SUGGEST       (TRUE | FALSE)      #IMPLIED
>
```

Attributes

The following sections describe the DIMSEARCH_CONFIG element's attributes.

FILTER_FOR_ANCESTORS

When set to TRUE, the results of a dimension search return only the highest ancestor dimension value. This means that if both red zinfandel and red wine match a search query for "red" and FILTER_FOR_ANCESTORS is set to true, only the red wine dimension value is returned. When set to FALSE, then both dimension values are returned. The default value is FALSE.

SEARCH_INERT_DVALS

When set to TRUE, certain non-navigable dimension values, such as dimension roots, are also returned as the result of a dimension search query. The default value is FALSE.

RELRANK_STRATEGY

Specifies the name of a relevance ranking strategy for dimension search.

RETURN_RELRANK_SCORE

Specifies that dimension search results should include the score assigned to each result by the relevance ranking system. Setting this value to TRUE is the same as running the Dgraph with the --stat-rel flag. The default value is FALSE.

ENABLE_AUTO_SUGGEST

Specifies whether automatic spelling correction is enabled for dimension searches. TRUE enables automatic spelling correction. FALSE disables it.

Sub-elements

The following table provides a brief overview of the DIMSEARCH_CONFIG sub-elements.

Sub-element	Brief description
COMMENT	Associates a comment with a parent element and preserves the comment when the file is rewritten. This element provides an alternative to using inline XML comments of the form <!-- ... -->.
PARTIAL_MATCH	Specifies if partial query matches should be supported for the dimension.
AUTO_SUGGEST	Specifies how to configure automatic spelling correction for either record searches or dimension searches.

Example

This example shows a configuration that displays ancestor dimension values but disables auto suggest recommendations.

```
<DIMSEARCH_CONFIG FILTER_FOR_ANCESTORS="FALSE" SEARCH_INSERT_DVALS="FALSE"
    ENABLE_AUTO_SUGGEST="FALSE" />
```

Dimsearch_index.xml elements

The Dimsearch_index.xml file specifies how Dgidx should index dimensions for dimension searches.

If you modify this file, you must re-index your data for the changes to take effect. Dgidx should index dimensions for dimension searches.

DIMSEARCH_HIERARCHY

A DIMSEARCH_HIERARCHY element returns the specified dimension values when a search matches multiple dimension values in a data hierarchy.

DTD

```
<!ELEMENT DIMSEARCH_HIERARCHY EMPTY>
<!ATTLIST DIMSEARCH_HIERARCHY
    NAME      CDATA      #REQUIRED
>
```

Attributes

The following sections describe the DIMSEARCH_HIERARCHY element's attribute.

NAME

Specifies the name of a dimension.

Sub-elements

DIMSEARCH_HIERARCHY contains no sub-elements.

Example

```
<DIMSEARCH_INDEX COMPOUND="FALSE" DICTIONARY_MAX_NGRAM_LENGTH="5" DICTIONARY_WILDCARD="TRUE"
INMEM_INDEX_THRESHOLD="512" MAX_NGRAM_LENGTH="3" MAX_WORD_LENGTH="16"
MIN_WORD_LENGTH="3"
MIN_WORD_OCCURRENCES="1" >
  <SEARCH_INDEX />
  <DIMSEARCH_HIERARCHY NAME="Review Score" />
</DIMSEARCH_INDEX>
```

DIMSEARCH_INDEX

A DIMSEARCH_INDEX element controls the behavior of search on a dimension.

DTD



Note: Several settings in this element are ignored starting with the MDEX Engine version 6.1.2. These settings are: MAX_NGRAM_LENGTH, DICTIONARY_MAX_NGRAM_LENGTH, and DICTIONARY_WILDCARD. Do not remove these settings from the file, since the DTD depends on them. Starting with the version 6.1.2, the MDEX Engine uses a simplified mechanism for wildcard search. This mechanism does not require specifying these settings. For more information on wildcard search, see the *Endeca MDEX Engine Basic Development Guide* version 6.1.2 or higher.

```
<!ELEMENT DIMSEARCH_INDEX (COMMENT?, SEARCH_INDEX, DIMSEARCH_HIERARCHY*) >
<!ATTLIST DIMSEARCH_INDEX
  COMPOUND          ( TRUE | FALSE )      "FALSE"
  INMEM_INDEX_THRESHOLD      CDATA      #IMPLIED
  MAX_NGRAM_LENGTH        CDATA      #IMPLIED
  DICTIONARY_WILDCARD      ( TRUE | FALSE )  #IMPLIED
  DICTIONARY_MAX_NGRAM_LENGTH  CDATA      #IMPLIED
  MIN_WORD_OCCURRENCES      CDATA      #IMPLIED
  MIN_WORD_LENGTH        CDATA      #IMPLIED
  MAX_WORD_LENGTH        CDATA      #IMPLIED
  >
```

Attributes

The following sections describe the attributes of the DIMSEARCH_INDEX element.

COMPOUND

Specifies whether the dimension is enabled for compound dimension searches. This extends a default dimension search which returns single dimensions. The default value is FALSE.

INMEM_INDEX_THRESHOLD

In MDEX Engine 6.4.0, this attribute was deprecated. Specifies the maximum text size (in MB) for which text indexing will be done entirely in memory. If the text size is larger than this threshold, then temporary files on disk will be used. Typically, you do not need to modify the value of this attribute. However, there are two infrequent scenarios in which you may want to adjust the value of this attribute:

- If the machine running Dgidx has less than the recommended about of RAM, you might reduce this value.
- If other indexing structures cause Dgidx to run out of memory, you might reduce this value to allow more memory for other purposes.

MAX_NGRAM_LENGTH

 **Note:** The value specified in this setting is ignored in the MDEX Engine starting with its version 6.1.2. However, do not remove this XML setting.

Specifies the maximum ngram length that should be indexed. The default value is 3. All substrings of this length or shorter will be indexed. If a user does a wildcard search with a string that is less than or equal to this length, then exact results can be returned directly from the index. If the wildcard search includes a substring longer than this length, then the results returned from the index will be post-processed so that false positives are eliminated.

DICTIONARY_WILDCARD

 **Note:** The value specified in this setting is ignored in the MDEX Engine starting with its version 6.1.2. However, do not remove this XML setting.

Specifies whether a wildcard index should be generated for the dictionary of words for the text collection containing this element. The default value of this attribute is TRUE when the containing element consists of off-line documents and FALSE otherwise.

DICTIONARY_MAX_NGRAM_LENGTH

 **Note:** The value specified in this setting is ignored in the MDEX Engine starting with its version 6.1.2. However, do not remove this XML setting.

Specifies the maximum ngram length that should be indexed in the dictionary wildcard index. The default value is 5.

MIN_WORD_OCCURRENCES

Specifies the minimum number of times a word must occur for it to be indexed for spelling correction. The default value is 1.

MIN_WORD_LENGTH

Specifies the minimum number of a characters that a word must contain for it to be indexed for spelling correction. The default value is 3 (words that are three characters or larger are added to the index).

MAX_WORD_LENGTH

Specifies the maximum number of a characters that a word may contain for it to be indexed for spelling correction. The default value is 16 (words that are 16 characters or fewer are added to the index).

Sub-elements

The following table provides a brief overview of the DIMSEARCH_INDEX sub-elements.

Sub-element	Brief description
COMMENT	Associates a comment with a parent element and preserves the comment when the file is rewritten. This element provides an alternative to using inline XML comments of the form <!-- ... -->.
SEARCH_INDEX	Controls the construction of the search index for dimension search.
DIMSEARCH_HIERARCHY	Returns the specified dimension values when a search matches multiple dimension values in a data hierarchy.

Example

```
<DIMSEARCH_INDEX COMPOUND="FALSE" DICTIONARY_MAX_NGRAM_LENGTH="5" DICTIONARY_WILDCARD="TRUE"
INMEM_INDEX_THRESHOLD="512" MAX_NGRAM_LENGTH="3" MAX_WORD_LENGTH="16"
MIN_WORD_LENGTH="3"
MIN_WORD_OCCURRENCES="1" >
  <SEARCH_INDEX/>
</DIMSEARCH_INDEX>
```

Dval_ranks.xml elements

The Dval_ranks.xml file assigns static ranking to dimension values.

Static ranking defines the order in which dimensions and dimension values appear in the user interface. Each dimension's rank is specified in a DVAL_RANK element. DVAL_RANK elements are grouped in the DVAL_RANKS root element. For more information, see "Using Relevance Ranking" in the *Endeca MDEX Engine Advanced Development Guide*.

DVAL_RANK

A DVAL_RANK element specifies a rank value for the root dimension value of a dimension. That same rank value also determines how dimensions are ordered within a dimension group. The order of the dimension groups is determined by the highest ranked dimension within each group.

DTD

```
<!ELEMENT DVAL_RANK EMPTY>
<!ATTLIST DVAL_RANK
  ID      CDATA      #REQUIRED
  RANK    CDATA      #REQUIRED
>
```

Attributes

The following sections describe the DVAL_RANK element's attribute.

ID

Specifies the dimension value ID.

RANK

Specifies the rank of this dimension value. This integer value determines how dimension values should be ranked when returned as refinements.

Sub-elements

DVAL_RANK contains no sub-elements.

Example

This example shows how dimension values are ranked in the wine reference implementation.

```
<DVAL_RANKS>
  <DVAL_RANK ID="30" RANK="1" />
  <DVAL_RANK ID="28" RANK="3" />
  <DVAL_RANK ID="27" RANK="4" />
  <DVAL_RANK ID="29" RANK="2" />
  <DVAL_RANK ID="26" RANK="5" />
  <DVAL_RANK ID="25" RANK="6" />
  <DVAL_RANK ID="24" RANK="7" />
  <DVAL_RANK ID="23" RANK="8" />
  <DVAL_RANK ID="22" RANK="9" />
  <DVAL_RANK ID="21" RANK="11" />
  <DVAL_RANK ID="8000" RANK="10" />
  <DVAL_RANK ID="10" RANK="9" />
  <DVAL_RANK ID="2" RANK="8" />
</DVAL_RANKS>
```

DVAL_RANKS

A DVAL_RANKS element contains any number of dimension value rankings indicated by DVAL_RANK elements.

DTD

```
<!ELEMENT DVAL_RANKS (COMMENT?, DVAL_RANK*)>
```

Attributes

The DVAL_RANKS element has no attributes.

Sub-elements

The following table provides a brief overview of the DVAL_RANKS sub-elements.

Sub-element	Brief description
COMMENT	Associates a comment with a parent element and preserves the comment when the file is rewritten. This element provides an alternative to using inline XML comments of the form <!-- ... -->.
DVAL_RANK	Specifies a rank value for the root dimension value of a dimension.

Example

This example shows how dimension values are ranked in the wine reference implementation.

```
<DVAL_RANKS>
  <DVAL_RANK ID="30" RANK="1" />
  <DVAL_RANK ID="28" RANK="3" />
  <DVAL_RANK ID="27" RANK="4" />
  <DVAL_RANK ID="29" RANK="2" />
  <DVAL_RANK ID="26" RANK="5" />
```

```

<DVAL_RANK ID="25" RANK="6" />
<DVAL_RANK ID="24" RANK="7" />
<DVAL_RANK ID="23" RANK="8" />
<DVAL_RANK ID="22" RANK="9" />
<DVAL_RANK ID="21" RANK="11" />
<DVAL_RANK ID="8000" RANK="10" />
<DVAL_RANK ID="10" RANK="9" />
<DVAL_RANK ID="2" RANK="8" />
</DVAL_RANKS>

```

Dval_refs.xml elements

The Dval_refs.xml file contains a DVAL_REF element for every dimension value in your hierarchy.

The DVAL_REF element allows you to specify a dimension value's ID, whether it is navigable or not, and whether it is collapsible or not. DVAL_REF elements are grouped in the DVAL_REFS parent element.

DVAL_REF

The DVAL_REF element specifies how individual dimension values behave.

DTD

```

<!ELEMENT DVAL_REF EMPTY>
<!ATTLIST DVAL_REF
  ID          CDATA          #REQUIRED
  INERT       (TRUE | FALSE)  "FALSE"
  COLLAPSIBLE (TRUE | FALSE)  "FALSE"
>

```

Attributes

The following sections describe the DVAL_REF attributes.

ID

Specifies the dimension value ID.

INERT

Specifies whether this dimension value is navigable. TRUE indicates the dimension value is not navigable. The default value is FALSE.

COLLAPSIBLE

COLLAPSIBLE is used in combination with the DVAL_COLLAPSE_THRESHOLD attribute on REFINEMENTS. Marking an internal dimension value as collapsible means that if the navigation state returns more child dimension values than of value specified in DVAL_COLLAPSE_THRESHOLD of REFINEMENTS, then collapsible dimension value is returned instead of the child dimension values.

Note that the DVAL_COLLAPSE_THRESHOLD, which is set at the dimension level, applies to all dimension values in that dimension. Each dimension value within a dimension may be marked as COLLAPSIBLE or not. See the DVAL_COLLAPSE_THRESHOLD description of REFINEMENTS for an example.

Sub-elements

DVAL_REF contains no sub-elements.

Example

This example shows a number of DVAL_REF elements that are collapsible.

```
<DVAL_REFS>
  <DVAL_REF ID="900024" COLLAPSIBLE="TRUE" />
  <DVAL_REF ID="900015" COLLAPSIBLE="TRUE" />
  <DVAL_REF ID="900006" COLLAPSIBLE="TRUE" />
  <DVAL_REF ID="900021" COLLAPSIBLE="TRUE" />
  <DVAL_REF ID="900009" COLLAPSIBLE="TRUE" />
  <DVAL_REF ID="900016" COLLAPSIBLE="TRUE" />
  <DVAL_REF ID="900012" COLLAPSIBLE="TRUE" />
  <DVAL_REF ID="900002" COLLAPSIBLE="TRUE" />
  <DVAL_REF ID="900007" COLLAPSIBLE="TRUE" />
</DVAL_REFS>
```

DVAL_REFS

A DVAL_REFS element contains any number of dimension value references indicated by DVAL_REF elements.

DTD

```
<!ELEMENT DVAL_REFS (COMMENT?, DVAL_REF*)>
```

Attributes

The DVAL_REFS element has no attributes.

Sub-elements

The following table provides a brief overview of the DVAL_REFS sub-elements.

Sub-element	Brief description
COMMENT	Associates a comment with a parent element and preserves the comment when the file is rewritten. This element provides an alternative to using inline XML comments of the form <!-- ... -->.
DVAL_REF	Specifies how individual dimension values behave.

Example

This example shows a number of DVAL_REF elements contained in a parent DVAL_REFS element.

```
<DVAL_REFS>
  <DVAL_REF ID="900024" COLLAPSIBLE="TRUE" />
  <DVAL_REF ID="900015" COLLAPSIBLE="TRUE" />
  <DVAL_REF ID="900006" COLLAPSIBLE="TRUE" />
  <DVAL_REF ID="900021" COLLAPSIBLE="TRUE" />
  <DVAL_REF ID="900009" COLLAPSIBLE="TRUE" />
  <DVAL_REF ID="900016" COLLAPSIBLE="TRUE" />
  <DVAL_REF ID="900012" COLLAPSIBLE="TRUE" />
  <DVAL_REF ID="900002" COLLAPSIBLE="TRUE" />
</DVAL_REFS>
```

```
<DVAL_REF ID="900007" COLLAPSIBLE="TRUE" />
</DVAL_REFs>
```

Externaldimension elements

The externaldimensions.xml file provides a means to create dimension hierarchies outside of Developer Studio.

You can then import an externally created dimension into your project and use it in your Endeca application. The XML elements in this file are documented in the "Working with Externally Created Dimensions" chapter of the *Endeca Forge Guide*.

Key_props.xml elements

The key_props.xml file allows property and dimension keys to be annotated with metadata key/value pairs called key properties (since they are properties of a dimension or property key).

These key properties are configured as PROP elements as part of the application configuration. The XML elements in this file are documented in the "Configuring Key Properties" chapter of the *Endeca MDEX Engine Analytics Guide*.

Languages.xml elements

The Languages.xml file specifies language identification codes for values in named dimensions or properties.

This identification allows a single MDEX Engine to contain records in multiple languages. The root element of Languages.xml is LANGUAGES. Within LANGUAGES, you specify associations between a dimension or property and a language using KEY_LANGUAGE. For more information, see "Using Internationalized Data" in the *Endeca Advanced Development Guide*.

KEY_LANGUAGE

The KEY_LANGUAGE element instructs the MDEX Engine to treat values from a specified dimension or property as values from a specified language.

The NAME attribute specifies the dimension or property. The LANGUAGE attribute specifies the code for the language. This association is useful when Endeca records in a number of languages are handled by a single dgraph instance.

DTD

```
<!ELEMENT KEY_LANGUAGE EMPTY>
<!ATTLIST KEY_LANGUAGE
  NAME          CDATA      #REQUIRED
  LANGUAGE      CDATA      #REQUIRED
>
```

Attributes

The following section describes the KEY_LANGUAGE element's attributes.

NAME

Specifies either a dimension or a property name to associate with a LANGUAGE value.

LANGUAGE

Specifies the language code for values represented in the dimension or property. ISO 639 lists the valid language codes. Common examples include the following: `en` for English, `es` for Spanish, `fr` for French, `de` for German, `ja` for Japanese, and `ko` for Korean. Chinese has two available codes: `zh-CN` for simplified Chinese and `zh-TW` for traditional Chinese.



Note: Language codes are case-sensitive and should be specified in lower case with the exception of `zh-TW` and `zh-CN`.

Sub-elements

The KEY_LANGUAGE element has no sub-elements.

Example

This example instructs the MDEX Engine to treat values in dimension called "Title_English" as English language values, and treat values in dimension called "Title_Spanish" as Spanish language values.

```
<LANGUAGES>
  <KEY_LANGUAGE NAME="Title_English" LANGUAGE="en" />
  <KEY_LANGUAGE NAME="Title_Spanish" LANGUAGE="es" />
</LANGUAGES>
```

LANGUAGES

The LANGUAGES element lists all of the language associations between a dimension or property and a particular language.

DTD

```
<!ELEMENT LANGUAGES (COMMENT?, KEY_LANGUAGE*)>
```

Attributes

The LANGUAGES element has no attributes.

Sub-elements

The following table provides a brief overview of the LANGUAGES sub-elements.

Sub-element	Brief description
COMMENT	Associates a comment with a parent element and preserves the comment when the file is rewritten. This element provides an alternative to using inline XML comments of the form <!-- ... -->.
KEY_LANGUAGE	Instructs the MDEX Engine to treat values from a specified dimension or property as values from a specified language.

Example

This example instructs the MDEX Engine to treat values in dimension called "Title_English" as English language values and treat values in dimension called "Title_Spanish" as Spanish language values.

```
<LANGUAGES>
  <KEY_LANGUAGE NAME="Title_English" LANGUAGE="en" />
  <KEY_LANGUAGE NAME="Title_Spanish" LANGUAGE="es" />
</LANGUAGES>
```

Phrases.xml elements

The Phrases.xml file specifies the recipe for building the phrase dictionary that the MDEX Engine uses for the Automatic Phrasing feature.

The root element of Phrases.xml is PHRASES. Its sub-elements (PHRASE_ADDITIONS and DIMENSION_IMPORTS) allow you to specify phrase entries for use with the Automatic Phrasing feature. When automatic phrasing is implemented in an application, the MDEX Engine can suggest automatically phrased queries to a user or process automatically phrased queries by default. For more information, see the "Using Automatic Phrasing" chapter in the *Endeca MDEX Engine Advanced Development Guide*.

PHRASES

A PHRASES element specifies phrase entries for the phrase dictionary.

You use the Automatic Phrasing editor in Developer Studio to import phrases from an XML phrase file or extract phrases from dimensions.

DTD

```
<!ELEMENT PHRASES
  ( COMMENT?
    , PHRASE_ADDITIONS
    , DIMENSION_IMPORTS
  )
>
```

Attributes

The PHRASES element has no attributes.

Sub-elements

The following table provides a brief overview of the PHRASES sub-elements.

Sub-element	Brief description
COMMENT	Associates a comment with a parent element and preserves the comment when the file is rewritten. This element provides an alternative to using inline XML comments of the form <!-- ... -->.
PHRASE_ADDITIONS	Represents phrases that have been imported from an XML phrase file.

Sub-element	Brief description
DIMENSION_IMPORTS	Represents dimension names from which phrases will be extracted from their dimension values.

Example

This example shows two phrases ("Napa Valley" and "low tannin") that were added from a phrase file and one dimension ("Wine_Type") from which phrases will be extracted.

```
<PHRASES>
  <PHRASE_ADDITIONS>
    <PHRASE>Napa Valley</PHRASE>
    <PHRASE>low tannin</PHRASE>
  </PHRASE_ADDITIONS>
  <DIMENSION_IMPORTS>
    <DIMNAME>Wine_Type</DIMNAME>
  </DIMENSION_IMPORTS>
</PHRASES>
```

PHRASE_ADDITIONS

A PHRASE_ADDITIONS element specifies a phrase entry that was imported from an XML phrase file.

You can import phrases from an XML phrase file by using the Import Phrases dialog box in Developer Studio. The phrases are added to the phrase dictionary that the MDEX Engine uses for the Automatic Phrasing feature.

DTD

```
<!ELEMENT PHRASE_ADDITIONS (PHRASE*)>
```

Attributes

The PHRASE_ADDITIONS element has no attributes.

Sub-element

The following table provides a brief overview of the PHRASE_ADDITIONS sub-element.

Sub-element	Brief description
PHRASE	Specifies a phrase entry for the phrase dictionary. For details, see the PHRASE element which is a common element in the Common.dtd elements file.

Example

This example shows two phrases ("Napa Valley" and "low tannin") that were added from a phrase file.

```
<PHRASES>
  <PHRASE_ADDITIONS>
    <PHRASE>Napa Valley</PHRASE>
    <PHRASE>low tannin</PHRASE>
  </PHRASE_ADDITIONS>
  <DIMENSION_IMPORTS/>
</PHRASES>
```

DIMENSION_IMPORTS

A DIMENSION_IMPORTS element specifies dimension names from which phrases will be extracted from their dimension values.

The MDEX Engine adds each multi-term dimension value in a selected dimension to the phrase dictionary. Single-term dimension values are not included. For example, if you import a WineType dimension from a wine catalog, the MDEX Engine creates a phrase entry for multi-term names such as "Pinot Noir" but not for single-term names such as "Merlot".

DTD

```
<!ELEMENT DIMENSION_IMPORTS (DIMNAME*)>
```

Attributes

The DIMENSION_IMPORTS element has no attributes.

Sub-element

The following table provides a brief overview of the DIMENSION_IMPORTS sub-element.

Sub-element	Brief description
DIMNAME	Specifies a dimension name from which a phrase will be extracted for the phrase dictionary. For details, see the DIMNAME element which is a common element in the Common.dtd elements file.

Example

This example shows two dimensions ("Flavors" and "Wine_Type") from which phrases will be extracted.

```
<PHRASES>
  <PHRASE_ADDITIONS/>
  <DIMENSION_IMPORTS>
    <DIMNAME>Flavors</DIMNAME>
    <DIMNAME>Wine_Type</DIMNAME>
  </DIMENSION_IMPORTS>
</PHRASES>
```

Pipeline.epx elements

The Pipeline.epx file defines the entire data transformation process of your source data into navigable Endeca records.

Pipeline.epx describes file locations, file formats, any necessary data manipulation, property-to-dimension mapping, and many other components in the process. Using simple NAME attributes as cross-references, these components are linked together in a flow that suggests a "pipeline" feel.

Each element available for use in Pipeline.epx is fully described in its own help topic within this section. See "Pipeline Overview" in the *Endeca Forge Guide* for more detailed conceptual information.

DIMENSION_ADAPTER

A DIMENSION_ADAPTER element reads and writes dimension files in .xml or binary formats.

When the optional TRANSFORMER sub-element is included, a dimension adapter can read in .xml files from external taxonomies and from Stratify Taxonomy Manager.

DTD

```
<!ELEMENT DIMENSION_ADAPTER
  ( COMMENT?
  , DIMENSION_SOURCE?
  , TRANSFORMER?
  , PASS_THROUGH*
  )
>
<!ATTLIST DIMENSION_ADAPTER
  NAME          CDATA          #REQUIRED
  DIRECTION     ( INPUT | OUTPUT ) #REQUIRED
  URL           CDATA          #REQUIRED
  COL_DELIMITER CDATA          #IMPLIED
  ROW_DELIMITER CDATA          #IMPLIED
  REC_DELIMITER CDATA          #IMPLIED
  FORMAT         CDATA          #REQUIRED
  REQUIRE_DATA  ( TRUE | FALSE ) #IMPLIED
  %compression;
```

Attributes

The following sections describe the DIMENSION_ADAPTER element's attributes.

NAME

Identifies the DIMENSION_ADAPTER so that it can be referenced by other components in Pipeline.epx.

DIRECTION

Indicates either INPUT or OUTPUT depending on whether the adapter is reading dimensions (input) or writing dimensions (output).

URL

Specifies the location of the source data, in this case dimension files. The path is either an absolute path or a path relative to the location of the Pipeline.epx file. With an absolute path, the protocol must be specified in RFC 2396 syntax. Usually this means the prefix file:/// precedes the path to the data file. Relative URLs must not specify the protocol and are relative to the URL used to locate the Pipeline.epx file.

COL_DELIMITER

This attribute is not used.

ROW_DELIMITER

This attribute is not used.

REC_DELIMITER

This attribute is not used.

FORMAT

Specifies the way in which the source data is formatted. Valid values are INTERNAL_DIM_XML, EXTERNAL_DIM_XML, BINARY (a proprietary format), STRATIFY, and PERL. Each value has the following meaning:

- INTERNAL_DIM_XML indicates the .xml file was created using Developer Studio and therefore conforms to dimensions.dtd.
- EXTERNAL_DIM_XML indicates the .xml file was read in from an externally managed taxonomy. The TRANSFORMER sub-element specifies the .xsl stylesheet that converts .xml from an externally managed taxonomy to Endeca-compatible .xml. (The pipeline developer authors an .xsl stylesheet that converts the .xml to conform to external_dimensions.dtd.)
- STRATIFY indicates the .xml file was read in from a Stratify Taxonomy Manager. The TRANSFORMER sub-element converts the file from Stratify .xml to Endeca-compatible .xml. (Endeca provides an .xsl stylesheet that converts the .xml to conform to external_dimensions.dtd.)
- To use Perl code in a DIMENSION_ADAPTER, you must configure the PASS_THROUGH element with additional attribute values and also provide the code itself as the PCDATA of PASS_THROUGH.

REQUIRE_DATA

Set to TRUE by default, this attribute causes an error to generate if the URL does not exist or is empty. The attribute needs to be declared within a dimension adapter only if it is being set to FALSE (to turn the error off).

COMPRESSION_LEVEL

Controls the level of data compression when an adapter is configured for OUTPUT. The default compression level for this attribute is 0 (no compression). The value -1 for this attribute has been deprecated. Values 1-9 indicate increasing levels of compression.

Sub-elements

The following table provides a brief overview of the DIMENSION_ADAPTER sub-elements.

Sub-element	Brief description
COMMENT	Associates a comment with a parent element and preserves the comment when the file is rewritten. This element provides an alternative to using inline XML comments of the form <!-- ... -->.
DIMENSION_SOURCE	Specifies the name of a dimension adapter from which the component should read dimensions.
TRANSFORMER	Transforms source .xml data into Endeca-compatible .xml dimensions according to a specified .xslt style sheet.
PASS_THROUGH	In a DIMENSION_ADAPTER, the PASS_THROUGH element provides a means to run Perl code. Running Perl code in a dimension adapter is not supported.

Example

This example shows two DIMENSION_ADAPTER elements inputting dimension XML files to the pipeline.

```
<DIMENSION_ADAPTER URL="Dimension.xml" NAME="Dimensions" FORMAT="INTERNAL_DIM_XML"
DIRECTION="INPUT" />
<DIMENSION_ADAPTER URL="WineTypeDimension.xml" NAME="TypeDimension" FORMAT="INTERNAL_DIM_XML"
DIRECTION="INPUT" />
```

```
<DIMENSION_SERVER NAME="DimensionServer" FORMAT="INTERNAL_DIM_XML" PER-
SIST_URL=".../partition0/state/AutogenDimensions.xml">
  <DIMENSION_SOURCE>Dimensions</DIMENSION_SOURCE>
  <DIMENSION_SOURCE>TypeDimension</DIMENSION_SOURCE>
</DIMENSION_SERVER>
```

DIMENSION_SERVER

A DIMENSION_SERVER element provides a single point of reference for other components in Pipeline.epx to access dimensions.

The DIMENSION_SERVER must specify all necessary input DIMENSION_ADAPTER elements as its sources.

DTD

```
<!ELEMENT DIMENSION_SERVER
  ( COMMENT?
  , DVAL_ID_LIMITS?
  , DIMENSION_SOURCE+
  , NAV_CONFIG_SOURCE?
  )
>
<!ATTLIST DIMENSION_SERVER
  NAME          CDATA          #REQUIRED
  PERSIST_URL   CDATA          #IMPLIED
  FORMAT        ( XML | INTERNAL_DIM_XML | BINARY ) #IMPLIED
  MATCH_COUNT_LOG CDATA          #IMPLIED
  %compression;
```

Attributes

The following sections describe the DIMENSION_SERVER element's attributes.

NAME

Identifies the DIMENSION_SERVER so that it can be referenced by other pipeline components.

PERSIST_URL

Specifies the location of the persistent dimension data created by auto-generation. The path is either an absolute path, or a relative path. Relative paths are relative to the location of the Pipeline.epx file. With an absolute path the protocol may be specified in RFC 2396 syntax. Usually this means the prefix file:/// precedes the path to the data file.

FORMAT

Specifies the file format of the PERSIST_URL value. There are two valid values, INTERNAL_DIM_XML or BINARY. INTERNAL_DIM_XML indicates the file is stored as .xml that conforms to Endeca's .dtds. BINARY indicates the file is stored as a proprietary format that only the Endeca system can read and write.



Note: The XML format has been deprecated in favor of the INTERNAL_DIM_XML format.

MATCH_COUNT_LOG

Provides a name reference to a LOG component that tracks the number of dimension value to property value matches and writes them to log file.



Note: This attribute is deprecated and will be removed in a future release. See "Endeca Logging and Reporting System Overview" in the *Endeca Administration Guide* for details about how to implement logging in your Endeca application.

COMPRESSION_LEVEL

Controls the level of data compression when an adapter is configured for OUTPUT. The default compression level for this attribute is 0 (no compression). The value -1 for this attribute has been deprecated. Values 1-9 indicate increasing levels of compression.

Sub-elements

The following table provides a brief overview of the DIMENSION_SERVER sub-elements.

Sub-element	Brief description
COMMENT	Associates a comment with a parent element and preserves the comment when the file is rewritten. This element provides an alternative to using inline XML comments of the form <!-- ... -->.
DVAL_ID_LIMITS	Specifies the minimum and maximum dimension value IDs that Forge can assign during auto generation.
DIMENSION_SOURCE	Specifies the name of a dimension adapter from which the component should read dimensions

Example

This example shows a DIMENSION_SERVER element that contains sources naming two DIMENSION_ADAPTER inputs to the pipeline. Both sources are in .xml format.

```
<DIMENSION_SERVER NAME="DimensionServer" FORMAT="INTERNAL_DIM_XML" PER-
SIST_URL=".../partition0/state/AutoGenDimensions.xml">
  <DVAL_ID_LIMITS MIN="10000000" MAX="2147483647"/>
  <DIMENSION_SOURCE>Dimensions</DIMENSION_SOURCE>
  <DIMENSION_SOURCE>TypeDimension</DIMENSION_SOURCE>
</DIMENSION_SERVER>
```

DIMENSION_SOURCE

A DIMENSION_SOURCE element specifies the name of a dimension adapter from which a component should read dimensions.

For example, several DIMENSION_SOURCE elements may be nested within DIMENSION_SERVER and name several DIMENSION_ADAPTER elements as input to the Pipeline.epx file.

DTD

```
<!ELEMENT DIMENSION_SOURCE (#PCDATA)>
```

Attributes

The DIMENSION_SOURCE element has no attributes.

Sub-elements

The DIMENSION_SOURCE element has no sub-elements.

Example

This example shows two DIMENSION_SOURCE elements naming two DIMENSION_ADAPTER elements as input.

```
<DIMENSION_ADAPTER URL="Dimension.xml" NAME="Dimensions" FORMAT="XML" DIRECTION="INPUT" />
<DIMENSION_ADAPTER URL="WineTypeDimension.xml" NAME="TypeDimension" FORMAT="XML" DIRECTION="INPUT" />
<DIMENSION_SERVER NAME="DimensionServer" FORMAT="XML" PERSIST_URL=".../partition0/state/AutogenDimensions.xml">
  <DIMENSION_SOURCE>Dimensions</DIMENSION_SOURCE>
  <DIMENSION_SOURCE>TypeDimension</DIMENSION_SOURCE>
</DIMENSION_SERVER>
```

DVAL_ID_LIMITS

A DVAL_ID_LIMITS element specifies the minimum and maximum dimension value IDs that Forge can assign during auto generation.

DTD

```
<!ELEMENT DVAL_ID_LIMITS
  ( COMMENT?
    )
>
<!ATTLIST DVAL_ID_LIMITS
  MIN      CDATA      #REQUIRED
  MAX      CDATA      #REQUIRED
>
```

Attributes

The following sections describe the DVAL_ID_LIMITS element's attributes.

MIN

Indicates the minimum value that Forge can assign to a dimension value when auto generating IDs.

MAX

Indicates the maximum value that Forge can assign to a dimension value when auto generating IDs.

Sub-elements

The following table provides a brief overview of the DVAL_ID_LIMITS sub-element.

Sub-element	Brief description
COMMENT	Associates a comment with a parent element and preserves the comment when the file is rewritten. This element provides an alternative to using inline XML comments of the form <!-- ... -->.

Example

This example shows a DVAL_ID_LIMITS element constraining dimension value IDs to between 10000000 and 2147483647.

```
<DIMENSION_SERVER NAME="DimensionServer" FORMAT="XML" PERSIST_URL=".../partition0/state/AutogenDimensions.xml">
  <DVAL_ID_LIMITS MIN="10000000" MAX="2147483647" />
  <DIMENSION_SOURCE>Dimensions</DIMENSION_SOURCE>
  <DIMENSION_SOURCE>TypeDimension</DIMENSION_SOURCE>
</DIMENSION_SERVER>
```

EXPRBODY

An EXPRBODY element contains Perl code that manipulates data. Perl code is often useful if a data manipulation task is too complicated to perform in XML. EXPRBODY is a child of EXPRESSION.

DTD

```
<!ELEMENT EXPRBODY (#PCDATA)>
```

Attributes

The EXPRBODY element has no attributes.

Sub-elements

The EXPRBODY element has no sub-elements.

Example

This example shows the outline of an expression using Perl.

```
<EXPRESSION TYPE="VOID" NAME="PERL">
  <EXPRBODY>
    ...PERL code here...
  </EXPRBODY>
</EXPRESSION>
```

EXPRESSION

An EXPRESSION element instructs Forge about how to modify records.

EXPRESSION elements appear within record manipulators to specify the property values, dimension values, and records that are to be modified, and how to modify them. An expression consists of an EXPRESSION element with TYPE and NAME attributes. Expressions may contain EXPRNODE elements, which have NAME and VALUE attributes, to supply additional configuration information. There are several dozen individual expressions distinguished by their TYPE and NAME attributes. Each of these expressions is described in the *Endeca Data Foundry Expression Reference*.

Expressions may also contain other expressions; the contained expressions may provide values used by the containing expression, or the containing expression may provide control over which of the contained expressions are evaluated. See the *Endeca Data Foundry Expression Reference* for the full list of available expressions.



Note: Oracle recommends that you perform record manipulation with the PERL_MANIPULATOR element rather than with the EXPRESSION and RECORD_MANIPULATOR elements. However, if you need to access and modify dimension sources (e.g., a dimension adapter or dimension server), you should still use expressions such as DVAL PERL. The Perl manipulator does not access dimension sources.

DTD

```
<!ELEMENT DIMENSION_ADAPTER
  ( COMMENT?
  , EXPRBODY?
  , (EXPRNODE | EXPRESSION)*
  )
>
<!ATTLIST EXPRESSION
  TYPE ( PROPERTY
         | DVAL
         | INTEGER
         | STRING
         | STREAM
         | VOID
         | FLOAT )          #REQUIRED
  NAME      CDATA      #REQUIRED
  LABEL     CDATA      #IMPLIED
  URL       CDATA      #IMPLIED
>
```

Attributes

The following sections describe the EXPRESSION attributes.

TYPE

Describes the return value for the expression. For example, a FLOAT expression returns a floating point number. The valid values for TYPE are as follows: PROPERTY, DVAL, INTEGER, STRING, VOID, and FLOAT.



Note: STREAM is used internally by the MDEX Engine.

NAME

Describes the operation being performed. Expressions are typically referred to by the combination of their TYPE and NAME values (for example DVAL CONST). This combination helps to distinguish cases where there are several expressions with different TYPE values but the same NAME value (for example, DVAL CONST, FLOAT CONST, and INTEGER CONST). The *Endeca Data Foundry Expression Reference* contains a help topic for each NAME expression available.

URL

Used in Perl expressions. Specifies the URL (file) from which an expression can read Perl code. The code can be up to 65534 characters long.

Sub-elements

The following table provides a brief overview of the EXPRESSION sub-elements.

Sub-element	Brief description
COMMENT	Associates a comment with a parent element and preserves the comment when the file is rewritten. This element provides an alternative to using inline XML comments of the form <!-- ... -->.
EXPRBODY	Contains Perl code that manipulates data.
EXPRNODE	Provides a generic way of sending a variety of information to an EXPRESSION.
EXPRESSION	Instructs Forge about how to modify data in the Pipeline.epx file.

Example

This example shows a mathematical expression that adds two constant values (5 and 6).

```
<EXPRESSION TYPE="INTEGER" NAME="MATH">
  <EXPRNODE NAME="TYPE" VALUE="INTEGER" />
  <EXPRNODE NAME="OPERATOR" VALUE="ADD" />
  <EXPRESSION TYPE="INTEGER" NAME="CONST">
    <EXPRNODE NAME="VALUE" VALUE="5" />
  </EXPRESSION>
  <EXPRESSION TYPE="INTEGER" NAME="CONST">
    <EXPRNODE NAME="VALUE" VALUE="6" />
  </EXPRESSION>
</EXPRESSION>
```

This example adds a dimension value ID to the current record. The dimension value ID is determined by the mapping between the value of the P_Score property in the source data and the dimension values contained in the dimension with ID equal to 9.

```
<EXPRESSION NAME="ADD_DVAL" TYPE="VOID">
  <EXPRESSION NAME="MATCH" TYPE="DVAL">
    <EXPRNODE NAME="DIMENSION_ID" VALUE="9" />
    <EXPRESSION NAME="IDENTITY" TYPE="PROPERTY">
      <EXPRNODE NAME="PROP_NAME" VALUE="P_Score" />
    </EXPRESSION>
  </EXPRESSION>
</EXPRESSION>
```

EXPRNODE

An EXPRNODE element provides a generic way of sending a variety of information to an EXPRESSION.

The information could be descriptions, data types, constant values (parameters), and so on.

Comparatively speaking, this information is similar to a parameter for a function. See the *Endeca Data Foundry Expression Reference* for the full list of available expressions.

DTD

```
<!ELEMENT EXPRNODE (EXPRNODE*)>
<!ATTLIST EXPRNODE
  NAME          CDATA          #REQUIRED
  VALUE         CDATA          #IMPLIED
>
```

Attributes

The following sections describe the EXPRNODE attributes.

NAME

Describes the EXPRNODE element. Because EXPRNODE can be so broadly used to modify an expression, the NAME attribute varies in relation to the expression that it modifies. For example, NAME can specify a variety of values such as TYPE, NAME, OPERATOR, AUTO_GEN, OPERATION, and so on. See an expression's help topic for details about how the NAME attribute of an expression node modifies an expression.

VALUE

Provides a value that corresponds to the NAME attribute. Because EXPRNODE can be so broadly used, the VALUE attribute can specify a variety of values. For example, INTEGER may correspond to TYPE; SUM may correspond to NAME; ADD may correspond to OPERATOR, and so on. See an expression's help topic for details about how the VALUE attribute of an expression node modifies an expression.

Sub-elements

The EXPRNODE element can contain addition EXPRNODE elements as sub-elements.

Example

This example shows an expression adding a dimension value ID to the current record. The second and third expressions use EXPRNODE to provide name and value information for the parent EXPRESSION.

```
<EXPRESSION NAME="ADD_DVAL" TYPE="VOID">
  <EXPRESSION NAME="MATCH" TYPE="DVAL">
    <EXPRNODE NAME="DIMENSION_ID" VALUE="9" />
    <EXPRESSION NAME="IDENTITY" TYPE="PROPERTY">
      <EXPRNODE NAME="PROP_NAME" VALUE="P_Score" />
    </EXPRESSION>
  </EXPRESSION>
</EXPRESSION>
```

ID_SERVER

An ID_SERVER element specifies the location and format of the id-server.xml file.

The path is either an absolute path or a path relative to the location of the Pipeline.epx file. With an absolute path, the protocol must be specified in RFC 2396 syntax. Usually this means the prefix `file:///` precedes the path to the data file. Relative URLs must not specify the protocol and are relative to the URL used to locate the Pipeline.epx file.



Note: The ID_SERVER element has been deprecated.

DTD

```
<!ELEMENT ID_SERVER EMPTY>
<!ATTLIST ID_SERVER
  URL          CDATA          #REQUIRED
  FORMAT       CDATA          #REQUIRED
  REQUIRE_DATA ( TRUE | FALSE )  "FALSE"
>
```

Attributes

The following sections describe the ID_SERVER element's attributes.

URL

Specifies the location of the id-server file. The path is either an absolute path or a path relative to the location of the Pipeline.epx file. With an absolute path, the protocol must be specified in RFC 2396 syntax. Usually this means the prefix `file:///` precedes the path to the data file. Relative URLs must not specify the protocol and are relative to the URL used to locate the Pipeline.epx file.

FORMAT

Specifies the file format of id-server file. This value may be either XML or BINARY.

REQUIRE_DATA

Indicates whether the id-server.xml file must exist. If set to TRUE, Forge throws an error if the file is missing. If set to FALSE, Forge creates the file. The default is FALSE.

Sub-elements

The ID_SERVER element has no sub-elements.

Example

This example shows the id-server.xml file but does not require that it contain data.

```
<PIPELINE NAME="Sample Wine Pipeline">
  <LOG URL="../../logs/pipeline.log" NAME="LogFile" TYPE="UNIQUE" />
  <ID_SERVER URL="../partition0/state/id-server.xml"
    FORMAT="XML" REQUIRE_DATA="FALSE"/>
  ...Remainder of pipeline removed for simplicity...
</PIPELINE>
```

INDEXER_ADAPTER

An INDEXER_ADAPTER element writes records, dimensions, and index configuration information for further processing by Dgidx (the indexer).

For Dgidx to process output from the indexer adapter, the output format attributes must be configured as follows:

- Set the OUTPUT_RECORD_FORMAT to BINARY.
- Set the OUTPUT_DIMENSION_FORMAT attributes to XML.

Dgidx cannot process any other combinations of formats.

DTD

```
<!ELEMENT INDEXER_ADAPTER
  ( COMMENT?
  , RECORD_SOURCE
  , DIMENSION_SOURCE*
  , NAV_CONFIG_SOURCE?
  , PASS_THROUGH*
  , EXPRESSION*
  , RECORD_ID_SPEC?
  , RECORD_GROUP?
  , ROLLOVER?
  )>
```

```
>
<!ATTLIST INDEXER_ADAPTER
  NAME          CDATA          #REQUIRED
  FRC_PVAL_IDX  (TRUE | FALSE) "TRUE"
  OUTPUT_URL    CDATA          #IMPLIED
  OUTPUT_PREFIX CDATA          #IMPLIED
  OUTPUT_RECORD_FORMAT (XML | BINARY) "BINARY"
  OUTPUT_DIMENSION_FORMAT (XML | INTERNAL_DIM_XML) "INTERNAL_DIM_XML"
  MULTI         (TRUE | FALSE) #IMPLIED
  MULTI_PROP_NAME CDATA          #IMPLIED
  FILTER_UNKNOWN_PROPS (TRUE | FALSE) "TRUE"
  %compression;
>
```

Attributes

The following sections describe the INDEXER_ADAPTER element's attributes.

NAME

Identifies the INDEXER_ADAPTER so that it can be referenced by other components in Pipeline.epx.

FRC_PVAL_IDX

This attribute forces Forge to create a record or property index for better performance during processing. TRUE creates an index. FALSE lets Forge create indices when necessary. The default is TRUE.

OUTPUT_URL

Identifies the directory to which Forge writes its files and processed records. The path is either an absolute path or a path relative to the location of the Pipeline.epx file. With an absolute path, the protocol must be specified in RFC 2396 syntax. Usually this means the prefix `file:///` precedes the path to the data file. Relative URLs must not specify the protocol and are relative to the URL used to locate the Pipeline.epx file.

OUTPUT_PREFIX

Specifies the filename prefix to add when Forge writes its output files. The default is `out`.

OUTPUT_RECORD_FORMAT

Specifies the output format of the records Forge creates. The default is BINARY. Although BINARY is the most common output, it may be useful for troubleshooting to set the value to XML if you need to visually inspect the indexed records.

OUTPUT_DIMENSION_FORMAT

Specifies the output format of the dimensions file that Forge creates. The default value is INTERNAL_DIM_XML.



Note: The XML value is no longer used.

MULTI

Specifies whether multiple output files should be created. If MULTI="TRUE" then Forge checks MULTI_PROP_NAME for the location.

MULTI_PROP_NAME

Specifies a property name that indicates the location that a record coming through Forge should be written to. (Forge stores a property on each record that is the source URL for that record.) Setting this property is useful if you want to process multiple input files and also keep the output distinct. In such

cases, set MULTI="TRUE" and then set MULTI_PROP_NAME="propname" to specify the location that the given record coming through Forge should be written to.

For example, suppose you have an input files named datedfile#1.txt and datedfile#2.txt that are unique based on the date in the file name. Further suppose you set MULTI="TRUE", set MULTI_PROP_NAME="Absolute_url", and set OUTPUT_PREFIX="out" in an OUTPUT adapter. Forge processes the files from the Absolute_url value of the input directory and file name, and Forge writes out.datedfile#1.records.xml and out.datedfile#2.records.xml to the OUTPUT_URL. The output files contain only the processed records from their corresponding input files.

FILTER_UNKNOWN_PROPS

Specifies whether unmapped properties should be removed from the processed records. The default value is TRUE. If you are using a partial update pipeline, this value should be the same in both the baseline pipeline and the partial update pipeline.

COMPRESSION_LEVEL

Controls the level of data compression when the indexer adapter writes record data. The default compression level for this attribute is 0 (no compression). The value -1 for this attribute has been deprecated. Values 1-9 indicate increasing levels of compression.

Sub-elements

The following table provides a brief overview of the INDEXER_ADAPTER sub-elements.

Sub-element	Brief description
COMMENT	Associates a comment with a parent element and preserves the comment when the file is rewritten. This element provides an alternative to using inline XML comments of the form <!-- ... -->.
RECORD_SOURCE	Specifies the name of a pipeline component from which this component should read records.
DIMENSION_SOURCE	Specifies the name of a pipeline component from which the component should read dimensions.
PASS_THROUGH	This sub-element is no longer used as part of an indexer adapter.
EXPRESSION	This sub-element is no longer used as part of an indexer adapter.
RECORD_GROUP	Provides property and dimension keys for record grouping.
ROLLOVER	Controls the point at which record output gets rolled over to a new file, and which Dgidx (indexer) processes records.

Example

This example shows an indexer adapter configured with most of the default formats and elements that point to the source files for records, dimensions, and index configuration information.

```
<INDEXER_ADAPTER NAME="IndexerAdapter"
    OUTPUT_URL="../partition0/forge_output/"
    FRC_PVAL_IDX="TRUE" OUTPUT_PREFIX="wine"
    OUTPUT_RECORD_FORMAT="BINARY"
    OUTPUT_DIMENSION_FORMAT="INTERNAL_DIM_XML">
    <RECORD_SOURCE>RecordManipulator</RECORD_SOURCE>
    <DIMENSION_SOURCE>DimensionServer</DIMENSION_SOURCE>
</INDEXER_ADAPTER>
```

JAVA_MANIPULATOR

A JAVA_MANIPULATOR element executes code in a Java class to perform data manipulation on properties and records.

You can write your own custom Java class and have it executed with this component. Note that a pipeline can have multiple Java manipulators.

DTD

```
<!ELEMENT JAVA_MANIPULATOR
  ( COMMENT?
    , RECORD_SOURCE
    , PASS_THROUGH*
  )
>
<!ATTLIST JAVA_MANIPULATOR
  NAME          CDATA      #REQUIRED
  CLASS_NAME    CDATA      #IMPLIED
  JAVA_HOME     CDATA      #IMPLIED
  JAVA_CLASSPATH CDATA      #IMPLIED
>
```

Attributes

The following sections describe the JAVA_MANIPULATOR element's attributes.

NAME

Identifies the JAVA_MANIPULATOR so that it can be referenced by other components in the pipeline.

CLASS_NAME

Specifies a Java class name. When the Java manipulator runs, it loads and runs the specified class. The .jar file must be accessible via the file system on the machine where Forge is running.

If you place the class .jar file in a location other than the ENDECA_ROOT/lib/java directory, use the JAVA_CLASSPATH attribute to specify the location of the .jar file.

JAVA_HOME

Specifies the location of the Java runtime engine (JRE). If this attribute is not specified, the Java manipulator sets the location by looking for a setting in the following order:

1. The Forge --javaHome command-line parameter.
2. The ENDECA_ROOT\j2sdk directory.
3. The JAVA_HOME environment variable.

An error is logged if a Java home could not be found.

JAVA_CLASSPATH

Specifies the absolute path to the .jar file on every machine on which Forge runs. The .jar file must contain the class (and all other classes it depends on) specified in the CLASS_NAME attribute. If you use the Forge --javaClasspath flag, it overrides the JAVA_CLASSPATH attribute in the pipeline.

The default classpath points to all the .jar files in the ENDECA_ROOT/lib/java directory. If either the JAVA_CLASSPATH attribute or the Forge --javaClasspath flag is used, the specified classpath is prefixed to the default classpath.

Sub-elements

The following table provides a brief overview of the JAVA_MANIPULATOR sub-elements.

Sub-element	Brief description
COMMENT	Associates a comment with a parent element and preserves the comment when the file is rewritten. This element provides an alternative to using inline XML comments of the form <!-- ... -->.
RECORD_SOURCE	Specifies the name of a pipeline component from which this component should read records.
PASS_THROUGH	Provides additional parameters for the Java class.

Example

This example shows a Java manipulator that will execute the TermExtractor class, with four parameters being passed in.

```
<JAVA_MANIPULATOR
  CLASS_NAME="com.endeca.edf.termextractor.TermExtractor"
  NAME="TermExtractor">
<RECORD_SOURCE>LoadAllMainData</RECORD_SOURCE>
<PASS_THROUGH NAME="RECORD_SPEC_PROP_NAME">P_WineID</PASS_THROUGH>
<PASS_THROUGH NAME="TEXT_PROP_NAME">P_Description</PASS_THROUGH>
<PASS_THROUGH NAME="OUTPUT_PROP_NAME">P_Terms</PASS_THROUGH>
<PASS_THROUGH NAME="ALL_TERMS_OUTPUT_PROP_NAME">P_AllTerms</PASS_THROUGH>
</JAVA_MANIPULATOR>
```

JOIN_ENTRY

A JOIN_ENTRY element specifies the key used to join records from a RECORD_SOURCE.

For more information about joining source data, see the *Endeca Forge Guide*.

DTD

```
<!ELEMENT JOIN_ENTRY
  ( RECORD_SOURCE
    , KEY_DIMENSION*
  )
>
```

Attributes

The JOIN_ENTRY element has no attributes.

Sub-elements

The following table provides a brief overview of the JOIN_ENTRY sub-elements.

Sub-element	Brief description
RECORD_SOURCE	Specifies the name of a pipeline component from which this component should read records.
KEY_DIMENSION	Determines how records are to be compared by the join implementation.

Example

This example shows the join entries of three record sources being joined according to SID and ID keys.

```
<RECORD_JOIN JOIN_TYPE="LEFT_JOIN">
  <JOIN_ENTRY>
    <RECORD_SOURCE>rs-1</RECORD_SOURCE>
    <KEY_DIMENSION TYPE="PVAL" ID="sid"/>
  </JOIN_ENTRY>
  <JOIN_ENTRY>
    <RECORD_SOURCE>rs-2</RECORD_SOURCE>
    <KEY_DIMENSION TYPE="PVAL" ID="id"/>
  </JOIN_ENTRY>
  <JOIN_ENTRY>
    <RECORD_SOURCE>rs-3</RECORD_SOURCE>
    <KEY_DIMENSION TYPE="PVAL" ID="id"/>
  </JOIN_ENTRY>
</RECORD_JOIN>
```

PASS_THROUGH

A PASS_THROUGH element provides additional configuration information for a pipeline component.

A PASS_THROUGH element has many distinct functions depending on the format of your source data. The source data can be delimited, fixed width, Perl code, an ODBC or JDBC datasource, or a custom record adapter.

- For delimited source files that do not have a header row in the file, PASS_THROUGH specifies the header names. Provide a delimited string containing each header name for the source data. See the COL_DELIMITER attribute of the RECORD_ADAPTER for the appropriate delimiter of the string.
- For fixed-width source files, PASS_THROUGH specifies how to handle reading source data. For information on using PASS_THROUGH when reading fixed-width data, see the Endeca Developer's Studio Help.
- To run Perl code in expressions, the PASS_THROUGH element specifies the Perl code to run as its PCDATA.
- To extract source data from an ODBC datasource, use PASS_THROUGH elements specifies the SQL code to run to identify the DSN and the user name and password of the datasource.
- To extract source data from a JDBC datasource, use PASS_THROUGH elements to specify the JDBC driver, the database URL, and SQL to execute against the database. If necessary, you can create additional PASS_THROUGH sub-elements that specify user name and password parameters. Note that configuring user name and password parameters varies according to your JDBC driver. For example, with Oracle JDBC Thin drivers, the user name and password parameters are included as part of the DB_URL string rather than as separate PASS_THROUGH sub-elements. You may have to refer to the documentation for your JDBC driver type to determine exact configuration requirements. See the Example section below.
- For an EXCHANGE adapter, the PASS_THROUGH element specifies the a path to the Microsoft Exchange server and if authentication is required, PASS_THROUGH specifies a path to a key_ring.xml file. See the Example section below.
- For a custom record adapter of FORMAT type JAVA_ADAPTER, the adapter developer may choose to expose datasource parameters that a pipeline author can provide in PASS_THROUGH elements. See the *Endeca Content Adapter Developer's Guide* for more information.
- For a JAVA_MANIPULATOR, the pipeline author can provide parameters to the Java class.

DTD

```
<!ELEMENT PASS_THROUGH (#PCDATA)>
<!ATTLIST PASS_THROUGH
  NAME      CDATA      #REQUIRED
>
```

Attributes

The following section describes the PASS_THROUGH element's attributes.

NAME

Specifies a variety of parameters that correspond to the function of the PASS_THROUGH element in its parent element. The following values are possible:

- For delimited source files, NAME specifies a descriptive name for the header row. For fixed-width source files, you must use several PASS_THROUGH elements, each of which has a different NAME value. See "Preparing Your Source Data" in the Endeca Developer Studio Help.
- To run Perl code, NAME must be set to PERL.
- To run SQL code, NAME must be set to SQL.
- To pass parameters in a JAVA_MANIPULATOR to a Java class, NAME must be set to the name of the parameter.
- To access a Microsoft Exchange Server, NAME must be set to URL. The value of the NAME attribute is a path to the server. If authentication is required, then a second element is necessary where NAME must be set to KEY_RING. The value of the NAME attribute is a path to the key_ring.xml file. See the Example below.
- To access an ODBC data source, one PASS_THROUGH element must have NAME attribute set to SQL. Then a second PASS_THROUGH element is required to identify the DSN, user name, and password. Its NAME attribute must be set to DSN. Provide the DSN, user name, and password values as a semi-colon (;) separated list. You may need to refer to your data source documentation for the correct key values of user name and password. In many ODBC data sources, these key values are UID and PWD. See the Example section below.
- To access a JDBC data source, one PASS_THROUGH element must have NAME set to DB_DRIVER_CLASS where DB_DRIVER_CLASS is the fully qualified Java class name of the JDBC database driver to use. In another PASS_THROUGH element, NAME must be set to DB_URL (where DB_URL is the URL of the database to connect to).

Sub-elements

The PASS_THROUGH element has no sub-elements.

Examples

This example shows how a record adapter's PASS_THROUGH sub-element might be configured if the wine_data.txt file had no header information.

```
<RECORD_ADAPTER
  URL="..../incoming/wine_data.txt" NAME="LoadMainData"
  FORMAT="DELIMITED"
  DIRECTION="INPUT"
  COL_DELIMITER="|"
  ROW_DELIMITER="\n" FILTER_EMPTY_PROPS="TRUE"
  <PASS_THROUGH
    NAME="HEADER_ROW">WINE_ID|YEAR|WINE|WINERY|PRICE|SCORE|RE-
  GION</PASS_THROUGH>
</RECORD_ADAPTER>
```

This example shows how a record adapter's PASS_THROUGH sub-elements might be configured to access a Microsoft Exchange server.

```
<RECORD_ADAPTER
  NAME= "Exchange_Server"
  DIRECTION= "INPUT"
  FORMAT= "EXCHANGE"
  JAVA_HOME= "C:\\java">
  <PASS_THROUGH
    NAME="URL" >http://exchange.my.company.com/public</PASS_THROUGH>
  <PASS_THROUGH NAME="KEY_RING">path/key_ring.xml</PASS_THROUGH>
</RECORD_ADAPTER>
```

This example shows how a record adapter's PASS_THROUGH sub-elements might be configured to access a JDBC datasource via an Oracle JDBC Thin driver.

```
<RECORD_ADAPTER
  NAME= "JDBC_Datasource"
  DIRECTION= "INPUT"
  FORMAT= "JDBC"
  JAVA_HOME= "/usr/local/j2sdk"
  JAVA_CLASSPATH= "lib/oracle8i.zip"
  <PASS_THROUGH
    NAME="DB_DRIVER_CLASS">oracle.jdbc.driver.OracleDriver<c
  </PASS_THROUGH>
  <PASS_THROUGH NAME="DB_URL">
    jdbc:oracle:thin:username/password@127.0.0.1:1521:myOracleDatabase
  </PASS_THROUGH>
  <PASS_THROUGH
    NAME="SQL">SELECT * FROM DOCUMENTSET ORDER BY ID</PASS_THROUGH>
</RECORD_ADAPTER>
```

This example shows an input record adapter reading an ODBC datasource.

```
<RECORD_ADAPTER
  NAME= "ODBC_Source"
  FORMAT= "ODBC"
  DIRECTION= "INPUT"
  JAVA_HOME= "C:\\java">
  <PASS_THROUGH
    NAME="DSN" >Northwind;UID=john;PWD=sw0rdf1sh</PASS_THROUGH>
  <PASS_THROUGH NAME="SQL">
    SELECT CustomerID, CompanyName, ContactName, ContactTitle, Address,
    City, Region, PostalCode, Country, Phone FROM Customers
  </PASS_THROUGH>
</RECORD_ADAPTER>
```

PERL_MANIPULATOR

A PERL_MANIPULATOR element executes Perl code to perform data manipulation on properties and records

You can provide Perl code to the PERL_MANIPULATOR in any of the following three ways:

- Specify the code in the body of a PERL_METHOD element. This approach is useful for simpler data manipulation and cases where you want to keep the Perl code in the Pipeline.epx file.
- Specify the code in a Perl file (.pl) external to your Pipeline.epx file, and identify the file in the URL attribute of a PERL_METHOD element. This approach is useful if you want to maintain the Perl code outside the Pipeline.epx file or reuse the code by calling the file from more than one Pipeline.epx file.

- Specify the code in a Perl module (.pm), and identify the file in the CLASS_NAME attribute of a PERL_MANIPULATOR element. This approach is more useful in cases where the amount of Perl code is large or complex.

See the *Forge API Guide for Perl* for information about Perl methods available for data manipulation within the PERL_MANIPULATOR and PERL_METHOD elements.

DTD

```
<!ELEMENT PERL_MANIPULATOR
  ( COMMENT?
    , RECORD_SOURCE*
    , RECORD_INDEX?
    , PERL_METHOD*
  )
>
<!ATTLIST PERL_MANIPULATOR
  NAME          CDATA      #REQUIRED
  CLASS_NAME    CDATA      #IMPLIED
>
```

Attributes

The following sections describe the PERL_MANIPULATOR element's attributes.

NAME

Identifies the PERL_MANIPULATOR so that it can be referenced by other components in the pipeline. Do not use any spaces in the NAME of a Perl manipulator or the Perl code that Forge generates will be invalid.

CLASS_NAME

Specifies a class name of a Perl module that you can create to call your Prepare, Next_Record, Get_Records, and Finish methods. When the Perl Manipulator runs, it loads and runs the specified class.

The Perl class must be located on the machine running Forge. It is convenient to locate the .pm file in the same location as other Perl modules for Endeca (ENDECA_ROOT\lib\perl). Placing your .pm file in ENDECA_ROOT\lib\perl does not require any additional configuration for Forge to locate it. However, if you upgrade Forge, you will have to copy this file to another location and copy it back in after upgrading.

If you place the file in a location other than ENDECA_ROOT\lib\perl, you must modify Perl's library search path to include the path to the .pm file. You can modify the path by either modifying your PERLLIB environment variable or by running Forge with the --perllib command-line option and providing the path as an argument

Sub-elements

The following table provides a brief overview of the PERL_MANIPULATOR sub-elements.

Sub-element	Brief description
COMMENT	Associates a comment with a parent element and preserves the comment when the file is rewritten. This element provides an alternative to using inline XML comments of the form <!-- ... -->.
RECORD_SOURCE	Specifies the name of a pipeline component from which this component should read records.

Sub-element	Brief description
RECORD_INDEX	Specifies a key used to identify records for record retrieval. This element is required if the Perl manipulator is using the GET_RECORDS attribute of PERL_METHOD.
PERL_METHOD	Specifies Perl code that Forge executes to perform data manipulation on properties and records.

Examples

This example adds a record number property to each record as it is processed.

```
<PERL_MANIPULATOR NAME="PerlManipulator">
  <RECORD_SOURCE>LoadData</RECORD_SOURCE>
  <PERL_METHOD NAME="PREPARE">
    # Make sure we have exactly one record source
    if (scalar(@{ $this->record_sources }) != 1) {
      die("Perl Manipulator ", $this->name,
          " must have exactly one record source.");
    }
    # Keep the current record number in our context
    $this->context->{RECNO} = 0;
  </PERL_METHOD>
  <PERL_METHOD NAME="NEXT_RECORD">
    # Count this record
    ++$this->context->{RECNO};
    my $rec = $this->record_source(0)->next_record;
    # Careful: $rec will be undef if there are no more records
    if ($rec) {
      my $pval = new EDF::PVal("Record Number", $this->context->{RECNO});
      $rec->add_pvals($pval);
    }
    return $rec;
  </PERL_METHOD>
</PERL_MANIPULATOR>
```

This is another example that performs the same task of adding a record number property to each record; however, this example uses a subclass and the CLASS_NAME attribute to provide the code.

```
<PERL_MANIPULATOR NAME="PerlManip" CLASS_NAME="MyPerlManip">
  <RECORD_SOURCE>LoadData</RECORD_SOURCE>
</PERL_MANIPULATOR>
```

Where the contents of MyPerlManip.pm are as follows:

```
package MyPerlManip;
use EDF::Manipulator;
@ISA = qw(EDF::Manipulator);
sub new
{
  my $proto = shift;
  my $class = ref($proto) || $proto;
  my $this = {};
  bless($this, $class);
  $this->SUPER::init(@_);
  return $this;
}
sub prepare
{
  my $this = shift;
  if (scalar(@{ $this->record_sources }) != 1) {
```

```
    die("Perl Manipulator ", $this->name,
        " must have exactly one record source.");
    }
    $this->{RECNO} = 0;
}
sub next_record
{
    my $this = shift;
    ++$this->{RECNO};
    my $rec = $this->record_source(0)->next_record;
    if ($rec) {
        my $pval = new EDF::PVal("Record Number", $this->{RECNO});
        $rec->add_pvals($pval);
    }
    return $rec;
}
```

PERL_METHOD

A PERL_METHOD element specifies Perl code that Forge executes to perform data manipulation on properties and records.

A PERL_MANIPULATOR may contain up to four PERL_METHOD elements. Each PERL_METHOD element is distinguished by its NAME attribute which specifies when Perl code executes during record processing and how the PERL_METHOD retrieves records. You can provide Perl code either in the body of the element, or you can point to a .pl file with the URL attribute.

DTD

```
<!ELEMENT PERL_METHOD (#PCDATA)>
<!ATTLIST PERL_METHOD
  NAME      (PREPARE|FINISH|NEXT_RECORD|GET_RECORDS) #REQUIRED
  URL       CDATA          #IMPLIED
  COMPRESSED (TRUE|FALSE)  #IMPLIED
  ENCODING  CDATA          #IMPLIED
>
```

Attributes

The following sections describe the PERL_METHOD element's attributes.

NAME

Specifies one of four possible values that describe either when the Perl code runs or the way in which the Perl code retrieves records. The Perl code associated with any of these attributes can be specified in the body of the element or in a .pl file. The valid values of this attribute are as follows:

- PREPARE — Specifies that the code within this element should execute at the beginning of record processing. PREPARE is useful for pre-processing tasks such as ensuring the correct number of data sources or ensuring the data sources have the correct properties and property values in the expected locations and so on.
- NEXT_RECORD — Specifies that records should be returned from the RECORD_SOURCE in sequential order. Returns the `undef` value when no additional records are available.
- GET_RECORDS — Similar to NEXT_RECORD but instead specifies that records should be returned from the RECORD_SOURCE as identified by a record key. The key is specified in a RECORD_INDEX sub-element of PERL_MANIPULATOR.

- **FINISH** — Specifies that the code within this element should execute at the end of record processing. FINISH is useful for post-processing tasks, for example printing the total number of records processed.

URL

Specifies a path to the Perl file (.pl) from which the PERL_MANIPULATOR reads Perl code. This attribute is useful in cases where you prefer not to include the Perl code in the body of the PERL_METHOD element, but instead want to write the code in a file that is external to the Pipeline.epx. If you point to a .pl file, you can also specify optional COMPRESSION and ENCODING attributes for the file.

The path is either an absolute path or a path relative to the location of the Pipeline.epx file. With an absolute path, the protocol must be specified in RFC 2396 syntax. Usually this means the prefix `file:///` precedes the path to the data file. Relative URLs must not specify the protocol and are relative to the URL used to locate the Pipeline.epx file.

COMPRESSED

Specifies whether the Perl file being accessed is compressed. TRUE indicates the file is compressed and instructs Forge to uncompress it before processing. FALSE indicates the Perl file is not compressed. The default value is FALSE.

ENCODING

Specifies the character encoding of the Perl file, indicated in the URL attribute. Forge supports the same encodings for the PERL_MANIPULATOR and RECORD_ADAPTER. See the ENCODING attribute of the RECORD_ADAPTER for a full description of valid encodings.

Sub-elements

The PERL_METHOD element has no sub-elements.

Example

This example includes three PERL_METHOD elements, each of which refers to an individual .pl file to run the Perl code.

```
<PERL_MANIPULATOR NAME="PerlManipulator">
  <RECORD_SOURCE>LoadData</RECORD_SOURCE>
  <PERL_METHOD NAME="PREPARE" URL="prepare.pl"
    COMPRESSED="FALSE" ENCODING="ASCII">
  </PERL_METHOD>
  <PERL_METHOD NAME="NEXT_RECORD" URL="next_record.pl"
    COMPRESSED="FALSE" ENCODING="ASCII">
  </PERL_METHOD>
  <PERL_METHOD NAME="FINISH" URL="done.pl"
    COMPRESSED="FALSE" ENCODING="ASCII">
  </PERL_METHOD>
</PERL_MANIPULATOR>
```

PIPELINE

A PIPELINE element is the root element of a project's Pipeline.epx file.

The PIPELINE element contains all the components, expressed as sub-elements, that describe and control the data transformation process. Pipeline.epx may contain components in any order. The entire PIPELINE is a repeatable sequence. Although components may appear in any order in the XML, they

typically are ordered in a sequential flow to produce a "pipeline" feel. Actual execution flow is controlled by Forge and the way in which you connect components with naming references.

DTD

```
<!ELEMENT PIPELINE
  ( COMMENT?
    | LOG*
    | ID_SERVER
    | RECORD_ADAPTER+
    | RECORD_CACHE*
    | RECORD_ASSEMBLER*
    | RECORD_MANIPULATOR+
    | PROP_MAPPER+
    | PERL_MANIPULATOR+
    | JAVA_MANIPULATOR+
    | DIMENSION_ADAPTER+
    | DIMENSION_SERVER
    | INDEXER_ADAPTER
    | UPDATE_ADAPTER
    | SPIDER*
  )+
>
<!ATTLIST PIPELINE
  NAME      CDATA      #REQUIRED
>
```

Attributes

The following section describes the PIPELINE element's attribute.

NAME

A unique name describing the pipeline.

Sub-elements

The following table provides a brief overview of the PIPELINE sub-elements.

Sub-element	Brief description
COMMENT	Associates a comment with a parent element and preserves the comment when the file is rewritten. This element provides an alternative to using inline XML comments of the form <!-- ... -->.
LOG	Holds the information gathered by the INFO element. This element is deprecated.
ID_SERVER	Specifies the location and format of the id-server.xml file. This element is deprecated.
RECORD_ADAPTER	Reads and writes record data in a variety of formats.
RECORD_CACHE	Sorts records according to a specified key and loads the records in memory for join operations.
RECORD_ASSEMBLER	Assembles (joins) records from multiple sources together based on a specified index.

Sub-element	Brief description
RECORD_MANIPULATOR	Contains EXPRESSIONS, which are evaluated against each record as it flows through the pipeline. When an EXPRESSION is evaluated, it may modify the current record.
PROP_MAPPER	Maps properties from source data to Endeca properties and dimensions.
PERL_MANIPULATOR	Executes Perl code to perform data manipulation on properties and records.
JAVA_MANIPULATOR	Executes code in a Java class to perform data manipulation on properties and records.
DIMENSION_ADAPTER	Reads and writes dimension files in a variety of formats.
DIMENSION_SERVER	Provides both a single point of reference for other pipeline components to access dimensions.
INDEXER_ADAPTER	Writes records, dimensions, and navigation configuration information for further processing by Dgidx (the indexer).
UPDATE_ADAPTER	As part of a partial update pipeline, an UPDATE_ADAPTER element writes partial update information for a running Endeca MDEX Engine to perform a live update.
SPIDER	Adds the capability to crawl document hierarchies on a file system or on Web sites. This element is deprecated.

Example

This example shows the sub-elements in a pipeline.

```

<PIPELINE NAME="Sample Wine Pipeline">
  <INDEXER_ADAPTER COMPRESSION_LEVEL="0" FILTER_UNKNOWN_PROPS="TRUE"
    FRC_PVAL_IDX="TRUE" MULTI_PROP_NAME="" NAME="IndexerAdapter"
    OUTPUT_DIMENSION_FORMAT="XML" OUTPUT_PREFIX="wine"
    OUTPUT_RECORD_FORMAT="BINARY" OUTPUT_URL=".../partition0/forge_output/">

  <RECORD_SOURCE>PropDimMapper</RECORD_SOURCE>
  <DIMENSION_SOURCE>DimensionServer</DIMENSION_SOURCE>
  <ROLLOVER CUTOFF="2000000000" NAME="RECORD" NUM_IDX="1"
    PROP_NAME="" PROP_TYPE="ALPHA" REMOVE_PROP="FALSE" ROLL_URL=""
    TYPE="SIZE" VALIDATE="FALSE"/>
</INDEXER_ADAPTER>
<RECORD_ADAPTER COL_DELIMITER="|" DIRECTION="INPUT"
  FILTER_EMPTY_PROPS="TRUE" FORMAT="DELIMITED" FRC_PVAL_IDX="TRUE"
  NAME="LoadMainData" PREFIX="" REC_DELIMITER=" " ROW_DELIMITER="|\n"
  URL=".../incoming/wine_data.txt.gz">
  <COMMENT></COMMENT>
</RECORD_ADAPTER>
<DIMENSION_ADAPTER COL_DELIMITER=" " DIRECTION="INPUT"
  FORMAT="INTERNAL_DIM_XML" NAME="Dimensions" REC_DELIMITER=" "
  ROW_DELIMITER=" " URL="dimensions.xml">
  <COMMENT></COMMENT>
</DIMENSION_ADAPTER>
<DIMENSION_SERVER NAME="DimensionServer"
  COMPRESSION_LEVEL="0" FORMAT="INTERNAL_DIM_XML"
  PERSIST_URL=".../partition0/state/autogen_dimensions.xml">
  <COMMENT></COMMENT>
  <DIMENSION_SOURCE>Dimensions</DIMENSION_SOURCE>
</DIMENSION_SERVER>

```

```

<PROP_MAPPER DEFAULT_MAP_MODE="NONE" DEFAULT_MAX_LENGTH="">
  IMPLICIT_MAPPING="TRUE" NAME="PropDimMapper">
  <RECORD_SOURCE>LoadMainData</RECORD_SOURCE>
  <DIMENSION_SOURCE>DimensionServer</DIMENSION_SOURCE>
  <PROP_MAPPING_PROP MAX_LENGTH="0" PROP_NAME="P_Wine">
    TARGET_NAME="P_Name"/>
  <PROP_MAPPING_PROP MAX_LENGTH="0" PROP_NAME="P_Description">
    TARGET_NAME="P_Description"/>
  ...other PROP_MAPPER subelements removed for simplicity...
  <PROP_MAPPING_DIM MATCH_MODE="AUTO_GEN" MAX_LENGTH="0">
    PROP_NAME="P_Flavors" TARGET_NAME="Flavors"/>
</PROP_MAPPER>
</PIPELINE>

```

PROP_MAPPER

A PROP_MAPPER element maps properties from source data to Endeca properties and dimensions.

The mappings dictate which dimension values are tagged to the current record and which property information is available for record search and display. Source data properties may be mapped implicitly if the source property names are identical to Endeca dimension names. However, implicit mapping cannot take place between source data properties and Endeca properties.

There should be exactly one PROP_MAPPER element in a pipeline file. Use a single PROP_MAPPER element to map source properties to Endeca properties and Endeca dimensions. (Creating two PROP_MAPPER elements, one to map properties and one to map dimensions, causes errors for Dgidx.) Source properties may be mapped explicitly to Endeca properties and dimensions using PROP_MAPPING_PROP and PROP_MAPPING_DIM elements.

For details on the property mapper component, see the "Mapping Source Properties" chapter in the *Endeca Platform Services Forge Guide*.

DTD

```

<!ELEMENT PROP_MAPPER
  ( COMMENT?
    , RECORD_SOURCE
    , DIMENSION_SOURCE
    , RECORD_INDEX?
    , (PROP_MAPPING_NONE | PROP_MAPPING_PROP | PROP_MAPPING_DIM) *
  )
>
<!ATTLIST PROP_MAPPER
  NAME          CDATA          #REQUIRED
  IMPLICIT_MAPPING (TRUE | FALSE)  "TRUE"
  DEFAULT_MAP_MODE (NONE | PROP | DIM) "NONE"
  DEFAULT_MAX_LENGTH CDATA          #IMPLIED
>

```

Attributes

The following sections describe the PROP_MAPPER element's attributes.

NAME

Identifies the PROP_MAPPER so that it can be referenced by other components in the pipeline.

IMPLICIT_MAPPING

Specifies whether to create mappings between source properties and identically named Endeca dimensions. Implicit mapping cannot take place between source data properties and Endeca properties. Case sensitivity of the names matters. The default value is TRUE.

DEFAULT_MAP_MODE

Specifies how to map properties that are neither explicitly mapped with the PROP_MAPPING_PROP or PROP_MAPPING_DIM elements nor implicitly mapped with the IMPLICIT_MAPPING attribute. There are three valid values for this attribute: NONE, PROP, and DIM.

- NONE does not map properties that are explicitly or implicitly mapped. Unmapped properties are ignored during processing.
- PROP performs source property to Endeca property mapping. Forge does this by creating a PROP_MAPPING_PROP element, using the source property's name and value as the target Endeca property's name and value.
- DIM performs source property to Endeca dimension value mapping. Forge does this by creating a PROP_MAPPING_DIM element using the source property's name and value as the target dimension's name and dimension value.

DEFAULT_MAX_LENGTH

Specifies the maximum number of characters that the value of a source property may contain before it is not mapped to an Endeca property or dimension value. Forge ignores (does not map) source properties larger than this value.

This attribute is useful to prevent mapping large source properties. For example, if you set this value to 20 and Forge encounters a source property value that is longer than 20 characters, Forge does not map the source property. You can override DEFAULT_MAX_LENGTH for any explicit mapping by specifying a new value in the MAX_LENGTH attribute of PROP_MAPPING_DIM or PROP_MAPPING_PROP.

Setting DEFAULT_MAX_LENGTH or MAX_LENGTH to either zero (0) or an empty string ("") disables a maximum setting and defaults to the maximum allowable values for property or dimension mapping. The default maximum value for property mapping is an unlimited length. The default maximum value for dimension value mapping is 255 characters.

Sub-elements

The following table provides a brief overview of the PROP_MAPPER sub-elements.

Sub-element	Brief description
COMMENT	Associates a comment with a parent element and preserves the comment when the file is rewritten. This element provides an alternative to using inline XML comments of the form <!-- ... -->.
RECORD_SOURCE	Specifies the name of a pipeline component from which this component should read records.
DIMENSION_SOURCE	Specifies the name of a pipeline component from which the component should read dimensions.
RECORD_INDEX	Specifies a common key used to identify records during join operations, sort validation, and logging. When nested within PROP_MAPPER, the RECORD_INDEX element identifies records in log messages.
PROP_MAPPING_NONE	Prevents a source property from being mapped to an Endeca property or dimension.

Sub-element	Brief description
PROP_MAPPING_PROP	Maps a source property to an Endeca property.
PROP_MAPPING_DIM	Maps a source property to an Endeca dimension.

Examples

In this simple example, the PROP_MAPPER uses its default of implicit mapping to map all source properties to dimensions with the same name.

```
<PROP_MAPPER NAME="mapper" DEFAULT_MAP_MODE="DIM">
  <RECORD_SOURCE>data</RECORD_SOURCE>
  <DIMENSION_SOURCE>DimensionServer</DIMENSION_SOURCE>
</PROP_MAPPER>
```

In this more complicated example, the PROP_MAPPER maps the explicitly named source properties to named target properties and dimensions. All other source properties are mapped to dimensions of the same name because of the DEFAULT_MAP_MODE="DIM" setting. Source properties longer than 8 characters are not mapped..

```
<PROP_MAPPER NAME="mapper"
  DEFAULT_MAP_MODE="DIM"
  DEFAULT_MAX_LENGTH="8">
  <RECORD_SOURCE>data</RECORD_SOURCE>
  <DIMENSION_SOURCE>DimensionServer</DIMENSION_SOURCE>
  <PROP_MAPPING_PROP PROP_NAME="price" TARGET_NAME="Price"/>
  <PROP_MAPPING_DIM PROP_NAME="price" TARGET_NAME="Price Range"
    MATCH_MODE="NORMAL"/>
  <PROP_MAPPING_PROP PROP_NAME="sale_price" TARGET_NAME="Price"/>
  <PROP_MAPPING_DIM PROP_NAME="sale_price" TARGET_NAME="Price Range"
    MATCH_MODE="NORMAL"/>
</PROP_MAPPER>
```

PROP_MAPPING_DIM

A PROP_MAPPING_DIM element maps a source property to an Endeca dimension.

In this element, you specify matching configuration attributes including the name of the source property, the name of the target dimension, and the matching mode. To map source properties to Endeca properties, use the PROP_MAPPING_PROP element.

For details on the property mapper component, see the "Mapping Source Properties" chapter in the *Endeca Platform Services Forge Guide*.

DTD

```
<!ELEMENT PROP_MAPPING_DIM EMPTY>
<!ATTLIST PROP_MAPPING_DIM
  PROP_NAME   CDATA                      #REQUIRED
  TARGET_NAME CDATA                      #REQUIRED
  MAX_LENGTH  CDATA                      #IMPLIED
  MATCH_MODE  (NORMAL|MUST_MATCH|AUTO_GEN) "NORMAL"
>
```

Attributes

The following sections describe the PROP_MAPPING_DIM element's attributes.

PROP_NAME

Identifies the name of the source property to map.

TARGET_NAME

Identifies the name of the Endeca dimension that the source property is mapped to. Forge tags the record with dimension values from the target dimension that match the source property value. If the TARGET_NAME dimension does not exist, the property mapper creates it. The PROP_MAPPER ensures that a DIMENSION_REF and PRECEDENCE_RULE exist for the TARGET_NAME.

MAX_LENGTH

Specifies the maximum number of characters a source property's value may contain before it is not mapped to an Endeca dimension value. In addition to not being mapped, properties with values longer than MAX_LENGTH also generate a warning.

This attribute is useful to prevent mapping of large source properties. For example, if you set this value to 20 and Forge encounters a source property longer than 20 characters, Forge does not map that source property. Setting MAX_LENGTH to either zero (0) or an empty string ("") disables a maximum setting and defaults to the maximum allowable value for dimension mapping. The default maximum value for dimension value mapping is 255 characters.

MATCH_MODE

Specifies the match method for source data property. There are three valid values for this attribute: NORMAL, MUST_MATCH, and AUTO_GEN. The default value is NORMAL.

- NORMAL maps source property values that have a matching dimension value explicitly defined in the Dimension.xml file. Forge assigns the IDs specified in the Dimension.xml file to the Endeca records. Any source property values that do not have matching dimension values in the Dimension.xml file are ignored.
- MUST_MATCH behaves exactly as NORMAL; however, if a property value does not have a match, a warning is issued.
- AUTO_GEN automatically generates a dimension value name and ID for any source property value that does not have a matching dimension value in the Dimension.xml file.

Sub-elements

The PROP_MAPPING_DIM element has no sub-elements.

Example

This example shows several source properties being mapped to dimensions of a new name. Source properties longer than 8 characters are not mapped.

```
<PROP_MAPPER NAME="mapper" DEFAULT_MAP_MODE="DIM">
  <RECORD_SOURCE>data</RECORD_SOURCE>
  <DIMENSION_SOURCE>DimensionServer</DIMENSION_SOURCE>
  <PROP_MAPPING_PROP PROP_NAME="price" TARGET_NAME="Price" />
  <PROP_MAPPING_DIM PROP_NAME="price" TARGET_NAME="Price Range"
    MAX_LENGTH="8" MATCH_MODE="NORMAL"/>
  <PROP_MAPPING_PROP PROP_NAME="sale_price" TARGET_NAME="Price" />
  <PROP_MAPPING_DIM PROP_NAME="sale_price" TARGET_NAME="Price Range"
    MAX_LENGTH="8" MATCH_MODE="NORMAL"/>
</PROP_MAPPER>
```

PROP_MAPPING_NONE

A PROP_MAPPING_NONE element prevents a specified source property from being mapped to an Endeca property or dimension.

The PROP_MAPPING_NONE element provides a way to override mapping specified by the IMPLICIT_MAPPING or DEFAULT_MAP_MODE attributes of the PROP_MAPPER element. For example, you can set the PROP_MAPPER element's DEFAULT_MAP_MODE attribute to DIM and then prevent dimension mapping for specified source properties using a PROP_MAPPING_NONE element.

For details on the property mapper component, see the "Mapping Source Properties" chapter in the *Endeca Platform Services Forge Guide*.

DTD

```
<!ELEMENT PROP_MAPPING_NONE EMPTY>
<!ATTLIST PROP_MAPPING_NONE
  PROP_NAME  CDATA  #REQUIRED
>
```

Attributes

The following section describes the PROP_MAPPING_NONE element's attribute.

PROP_NAME

Identifies the source property that should not be mapped.

Sub-elements

The PROP_MAPPING_NONE element has no sub-elements.

Example

In this example, the reserve_price source property is excluded from mapping.

```
<PROP_MAPPER NAME="mapper" DEFAULT_MAP_MODE="DIM">
  <RECORD_SOURCE>data</RECORD_SOURCE>
  <DIMENSION_SOURCE>DimensionServer</DIMENSION_SOURCE>
  <PROP_MAPPING_PROP PROP_NAME="price" TARGET_NAME="Price" />
  <PROP_MAPPING_DIM PROP_NAME="price" TARGET_NAME="Price Range"
    MAX_LENGTH="8" MATCH_MODE="NORMAL" />
  <PROP_MAPPING_PROP PROP_NAME="sale_price" TARGET_NAME="Price" />
  <PROP_MAPPING_DIM PROP_NAME="sale_price" TARGET_NAME="Price Range"
    MAX_LENGTH="8" MATCH_MODE="NORMAL" />
  <PROP_MAPPING_NONE PROP_NAME="reserve_price" />
</PROP_MAPPER>
```

PROP_MAPPING_PROP

A PROP_MAPPING_PROP element maps a source property to an Endeca property.

In the PROP_MAPPING_PROP element, you specify matching configuration attributes including the name of the source property, the name of the target property, and the maximum length of the source property's value to be mapped. To map source properties to Endeca dimensions, use the PROP_MAPPING_DIM element.

For details on the property mapper component, see the "Mapping Source Properties" chapter in the *Endeca Forge Guide*.

DTD

```
<!ELEMENT PROP_MAPPING_PROP EMPTY>
<!ATTLIST PROP_MAPPING_PROP
  PROP_NAME   CDATA    #REQUIRED
  TARGET_NAME CDATA    #REQUIRED
  MAX_LENGTH  CDATA    #IMPLIED
>
```

Attributes

The following sections describe the PROP_MAPPING_PROP element's attributes.

PROP_NAME

Identifies the name of the source property to map.

TARGET_NAME

Identifies the name of the Endeca property that the source property value is mapped to. If the source and target properties have different names, Forge copies the source property value into the target property value. The PROP_MAPPER ensures that a PROP_REF exists for the TARGET_NAME.

MAX_LENGTH

Specifies the maximum number of characters a source property's value may contain before it is not mapped to an Endeca property. In addition to not being mapped, properties with values longer than MAX_LENGTH also generate a warning.

This attribute is useful to prevent mapping large source properties. For example, if you set this value to 20 and Forge encounters a source property with a value longer than 20 characters, Forge does not map the source property. Setting MAX_LENGTH to either zero (0) or an empty string ("") disables a maximum setting and defaults to the maximum allowable value for property mapping. The default maximum value for property mapping is unlimited.

Sub-elements

The PROP_MAPPING_PROP element has no sub-elements.

Example

This example shows several source properties being mapped to Endeca properties of a new name. Source properties with values longer than 8 characters are not mapped.

```
<PROP_MAPPER NAME="mapper" DEFAULT_MAP_MODE="DIM">
  <RECORD_SOURCE>data</RECORD_SOURCE>
  <DIMENSION_SOURCE>DimensionServer</DIMENSION_SOURCE>
  <PROP_MAPPING_PROP PROP_NAME="price" TARGET_NAME="Price" MAX_LENGTH="8" />
    <PROP_MAPPING_DIM PROP_NAME="price" TARGET_NAME="Price Range"
      MATCH_MODE="NORMAL" />
    <PROP_MAPPING_PROP PROP_NAME="sale_price" TARGET_NAME="Price"
      MAX_LENGTH="8" />
    <PROP_MAPPING_DIM PROP_NAME="sale_price" TARGET_NAME="Price Range"
      MATCH_MODE="NORMAL" />
  </PROP_MAPPER>
```

RECORD_ADAPTER

A RECORD_ADAPTER element reads and writes record data in a variety of formats.

The attributes of a RECORD_ADAPTER describe where the data is located, the format, and various aspects of processing.

DTD

```
<!ELEMENT RECORD_ADAPTER
  ( COMMENT?
    , RECORD_SOURCE?
    , DIMENSION_SOURCE?
    , RECORD_INDEX?
    , RECORD_GROUP?
    , TRANSFORMER?
    , PASS_THROUGH*
    , PROP_DECL*
  )
>
<!ATTLIST RECORD_ADAPTER
  NAME          CDATA          #REQUIRED
  FRC_PVAL_IDX  ( TRUE | FALSE ) "TRUE"
  DIRECTION     ( INPUT | OUTPUT ) #REQUIRED
  URL           CDATA          #IMPLIED
  STATE          ( TRUE | FALSE ) #IMPLIED
  PREFIX         CDATA          #IMPLIED
  COL_DELIMITER CDATA          #IMPLIED
  ROW_DELIMITER CDATA          #IMPLIED
  REC_DELIMITER CDATA          #IMPLIED
  FORMAT         CDATA          #REQUIRED
  ENCODING      CDATA          #IMPLIED
  REQUIRE_DATA   ( TRUE | FALSE ) #IMPLIED
  FILTER_EMPTY_PROPS ( TRUE | FALSE ) #IMPLIED
  MULTI          ( TRUE | FALSE ) #IMPLIED
  MULTI_PROP_NAME CDATA          #IMPLIED
  JAVA_HOME      CDATA          #IMPLIED
  JAVA_CLASSPATH CDATA          #IMPLIED
  JAVA_CLASSNAME CDATA          #IMPLIED
  %compression;
>
```

Attributes

The following sections describe the RECORD_ADAPTER element's attributes.

NAME

Identifies the RECORD_ADAPTER so that it can be referenced as a record source by other components in the pipeline.

FRC_PVAL_IDX

Forces Forge to create a record or property index for better performance during processing. TRUE always creates an index during processing. FALSE allows Forge to determine when an index would improve performance and to create it at that time.

DIRECTION

Indicates either INPUT or OUTPUT depending on whether the adapter is reading records (input) or writing records (output). If FORMAT is set to ODBC, then DIRECTION must be INPUT. If DIRECTION is set to output, then FORMAT must be either BINARY or XML.

URL

Specifies the location of the source data. The path is either an absolute path or a path relative to the location of the Pipeline.epx file. With an absolute path, the protocol must be specified in RFC 2396 syntax. Usually this means the prefix `file:///` precedes the path to the data file. Relative URLs must not specify the protocol and are relative to the URL used to locate the Pipeline.epx file.

STATE

Specifies the filename prefix to add when Forge writes its output files. The default is "out".

COL_DELIMITER

Indicates the character used to separate columns when using the DELIMITED or VERTICAL formats.

ROW_DELIMITER

Indicates the character used to separate rows when using the DELIMITED or VERTICAL formats.

REC_DELIMITER

Indicates the character or string used to separate records when using the VERTICAL format.

FORMAT

Specifies the way in which the source data is formatted. Valid values are as follows:

- BINARY - A proprietary format.
- DELIMITED - If you input delimited data, the COL_DELIMITER, and ROW_DELIMITER attributes are required for further configuration.
- FIXED-WIDTH - If you input fixed-width data, the PASS_THROUGH sub-element is required for further configuration.
- ODBC - Indicates that source data being read is a Windows ODBC datasource. This FORMAT requires two PASS_THROUGH sub-elements: one to specify the SQL that queries the ODBC datasource and another to identify the datasource name (DSN). See the Example section in PASS_THROUGH for a typical configuration. For information about which data types the ODBC and JDBC record adapters can fetch, see the table in the "JDBC and ODBC supported data types" section below.
- JDBC - Indicates that source data being read is a JDBC database. When using this format, you must specify a value for the JAVA_HOME and JAVA_CLASSPATH attributes. In addition, you must create PASS_THROUGH sub-elements that specify the JDBC driver, the database URL, and SQL to execute against the database. If necessary, you can create PASS_THROUGH sub-elements that specify user name and password parameters. See the Example section for PASS_THROUGH. For information about which data types the ODBC and JDBC record adapters can fetch, see the table in the "JDBC and ODBC supported data types" section below.
- JAVA_ADAPTER - Indicates that the data source being read is a custom record adapter that a developer created using the Endeca Record Adapter Developer Kit. When using this format, you must specify values for the JAVA_CLASSPATH, JAVA_CLASSNAME, and JAVA_HOME attributes. Depending on what other parameters the adapter developer decided to expose, there may be additional requirements specified in PASS_THROUGH sub-elements. See the *Endeca Content Adapter Developer's Guide* for more information.
- EXCHANGE - Indicates that the data source being read is a Microsoft Exchange server. When using this format, you must specify a value for the JAVA_HOME attribute and create PASS_THROUGH sub-elements that specify an HTTP path to the Exchange server and if authentication is required, specify a path to a key_ring.xml file.

- VERTICAL - Vertical data is a format that lists one property name and one property value per line, with records separated by a specified string on a line by itself. If you input vertical data, use the COL_DELIMITER attribute to separate property names from property values. Use the ROW_DELIMITER to identify the string used to separate lines; and use the REC_DELIMITER attribute to identify the string used to mark the end of a record.
- XML - If you input XML source data, the encoding value should be specified in the first line of the XML file.

ENCODING

Specifies the character encoding of the source data. When you provide source data, Forge requires the correct encoding value to read the data correctly. If you do not specify encoding, Forge defaults to Latin-1. The XML format has a standard for specifying the encoding in the first line of XML file. An ENCODING value is ignored for OUTPUT adapters and for the XML format.

When Forge crawls documents, it detects the encoding and stores an encoding value in a property on the record named Endeca.Document.Encoding. You do not need to specify an ENCODING value when crawling documents with a SPIDER.

Forge supports all encodings supported by International Components for Unicode (ICU). There are several hundred supported ENCODING values and more than 1000 aliases to those encoding values, all of which are valid input to the ENCODING attribute. Here are a few common examples of ENCODING values:

- ISO-8859-1 (Latin-1)
- ISO-8859-15 (Latin-9)
- WINDOWS-1252 (CP1252, WINDOWS-1252)
- ASCII (US-ASCII)
- UTF-8
- UTF-16
- Big5

The ENCODING attribute may be overridden when running Forge on the command-line using the --input-encoding flag. This flag overrides all encodings for all input adapters (except when the XML format is being used; see below). Both the ENCODING attribute and the --input-encoding flag are ignored for OUTPUT adapters and for the XML format.

REQUIRE_DATA

Set to TRUE by default, this attribute causes Forge to generate an error if the URL does not exist or is empty. The attribute needs to be declared within an adapter only if it is being set to FALSE (to turn the error off).

FILTER_EMPTY_PROPS

Set to FALSE by default, this attribute ensures that empty property values are not assigned to records. For example, if a record has no value for the "Colors" property, by default the record adapter assigns the property a value of "" (an empty string). Setting FILTER_EMPTY_PROPS to TRUE prevents this behavior. The value needs to be declared within a record adapter only if it is being set to TRUE.

The FILTER_EMPTY_PROPS attribute applies only to input record adapters (i.e., it does not apply to output record adapters). In addition, it is valid only for the Vertical, Delimited, Fixed-width, and ODBC input formats.

MULTI

Specifies whether Forge can read data from more than one input file. The default, FALSE, indicates that the URL is a single input file. If set to TRUE, the input URL is interpreted as a pattern, and Forge reads each file matching the pattern in sequence. For example, the record adapter may specify a URL

pattern of "*.update.txt", in which case Forge reads any file in the given directory that has the .update.txt suffix. This value must be set to TRUE if you want to use MULTI_PROP_NAME.

When used in an OUTPUT record adapter, the MULTI and MULTI_PROP_NAME attributes specify which file each record is written to. If MULTI="TRUE" then Forge checks MULTI_PROP_NAME for the location.

MULTI_PROP_NAME

Specifies a property name that indicates the location that a record coming through Forge should be written to. (Forge stores a property on each record that is the source URL for that record.) Setting this property is useful if you want to process multiple input files and also keep the output distinct. In such cases, set MULTI="TRUE" and then set MULTI_PROP_NAME="propname" to specify the location that the given record coming through Forge should be written to.

For example, suppose you have an input files named datedfile#1.txt and datedfile#2.txt that are unique based on the date in the file name. Further suppose you set MULTI="TRUE", set MULTI_PROP_NAME="Absolute_url", and set OUTPUT_PREFIX="out" in an OUTPUT adapter. Forge processes the files from the Absolute_url value of the input directory and file name, and Forge writes out.datedfile#1.records.xml and out.datedfile#2.records.xml to the OUTPUT_URL. The output files contain only the processed records from their corresponding input files.

STATE

TRUE indicates that the value of URL is relative to the Forge --stateDir flag. This allows you to change your state directory using the --stateDir flag and yet not require you to modify your record adapter configuration.

JAVA_HOME

Specifies the location of the Java runtime engine (JRE). For example, if you have the Java SDK installed, the attribute may be set to:

```
JAVA_HOME="C:\j2dk\jre"
```

If you have only the JRE installed, the attribute may be set to:

```
JAVA_HOME="C:\j2dk"
```

This attribute is required when FORMAT is set to JAVA_ADAPTER, JDBC, or EXCHANGE.

JAVA_CLASSPATH

When FORMAT="JAVA_ADAPTER", this attribute specifies the absolute path to the custom record adapter's .jar file on every machine on which Forge runs, as in this example:

```
JAVA_CLASSPATH="C:\Projects\lib\MyAdapter.jar"
```

The .jar file must contain the adapter class and all other classes it depends on.

When FORMAT="JDBC", this attribute specifies the location of the .jar file that contains the JDBC driver, as in this example:

```
JAVA_CLASSPATH="/usr/local/projects/lib/oracle8i.zip"
```

If the JDBC driver you are using is distributed with the JVM, you can omit this setting (for example, the jdbc-odbc bridge driver does not require a classpath).

This attribute is required when FORMAT is set to JAVA_ADAPTER.

JAVA_CLASSNAME

Specifies the name of the adapter class to load within the .jar file indicated by JAVA_CLASSPATH, as in this example:

```
JAVA_CLASSNAME="MyAdapter"
```

This attribute is required when FORMAT is set to JAVA_ADAPTER.

COMPRESSION_LEVEL

Controls the level of data compression when an adapter is configured for OUTPUT. The default compression level for this attribute is 0 (no compression). The value "-1" for this attribute has been deprecated. Values 1-9 indicate increasing levels of compression.

Sub-elements

The following table provides a brief overview of the RECORD_ADAPTER sub-elements.

Sub-element	Brief description
COMMENT	Associates a comment with a parent element and preserves the comment when the file is rewritten. This element provides an alternative to using inline XML comments of the form <!-- ... -->.
RECORD_SOURCE	Specifies the name of a pipeline component from which this component should read records.
DIMENSION_SOURCE	Specifies the name of a pipeline component from which the component should read dimensions.
RECORD_INDEX	Specifies the property and dimension keys on which record sorts are validated. Join operations also find records that share a common key based on the RECORD_INDEX element.
RECORD_GROUP	Provides property and dimension keys for record grouping.
TRANSFORMER	Transforms source XML data into Endeca-compatible XML records according to a specified XSLT style sheet.
PASS_THROUGH	Provides additional parameters for the Java class.

JDBC and ODBC supported data types

The following table provides information about supported data types for record adapters using either the JDBC or ODBC formats.

Data type	Supported?
CHAR	Yes, up to 1M bytes. Note that if a field in the result set is larger than 1MB (1,048,576 bytes), the result is truncated at that length.
VARCHAR	Yes, up to 1M bytes.
LONGVARCHAR (CLOB)	No
WCHAR	Yes, up to 1M bytes.
VARWCHAR	Yes, up to 1M bytes.
LONGWVARCHAR	No
DECIMAL	Yes
NUMERIC	Yes
SMALLINT	Yes
INTEGER	Yes

Data type	Supported?
REAL	Yes
FLOAT	Yes
DOUBLE	Yes
BIT	Yes
TINYBIT	Yes
BIGINT	No
BINARY	No
VARBINARY	No
LONGVARBINARY (BLOB)	No
DATE	Yes
TIME	Yes
TIMESTAMP	Yes
UTCDATETIME	No
UTCTIME	No
INTERVAL MONTH	No
INTERVAL YEAR	No
INTERVAL YEAR TO MONTH	No
INTERVAL DAY	No
INTERVAL HOUR	No
INTERVAL MINUTE	No
INTERVAL SECOND	No
INTERVAL DAY TO HOUR	No
INTERVAL DAY TO MINUTE	No
INTERVAL DAY TO SECOND	No
INTERVAL HOUR TO MINUTE	No
INTERVAL HOUR TO SECOND	No
INTERVAL MINUTE TO SECOND	No
GUID	Yes

Example

This example shows an input record adapter reading pipe-delimited text.

```
<RECORD_ADAPTER COL_DELIMITER=" | " DIRECTION="INPUT"
  FILTER_EMPTY_PROPS="TRUE" FORMAT="DELIMITED" FRC_PVAL_IDX="TRUE"
  NAME="LoadMainData" PREFIX="" REC_DELIMITER=" " ROW_DELIMITER=" | \n"
  URL="..../incoming/wine_data.txt.gz">
```

```
<COMMENT></COMMENT>
</RECORD_ADAPTER>
```

RECORD_ASSEMBLER

A RECORD_ASSEMBLER element assembles (joins) records from multiple sources together based on a specified index.

For more information about joining source data, see the *Endeca Forge Guide*.

DTD

```
<!ELEMENT RECORD_ASSEMBLER
  ( COMMENT?
    , RECORD_SOURCE+
    , DIMENSION_SOURCE?
    , RECORD_INDEX?
    , RECORD_JOIN
  )
>
<!ATTLIST RECORD_ASSEMBLER
  NAME          CDATA          #REQUIRED
  FRC_PVAL_IDX  (TRUE | FALSE)  "TRUE"
>
```

Attributes

The following sections describe the RECORD_ASSEMBLER element's attributes

NAME

Identifies the RECORD_ASSEMBLER so that it can be referenced as a record source by other pipeline components

FRC_PVAL_IDX

Forces Forge to create a record or property index for better performance during processing. TRUE always creates an index during processing. FALSE allows Forge to determine when an index would improve performance and to create it at that time.

Sub-elements

The following table provides a brief overview of the RECORD_ASSEMBLER sub-elements.

Sub-element	Brief description
COMMENT	Associates a comment with a parent element and preserves the comment when the file is rewritten. This element provides an alternative to using inline XML comments of the form <!-- ... -->.
RECORD_SOURCE	Specifies the name of a pipeline component from which this component should read records.
DIMENSION_SOURCE	Specifies the name of a pipeline component from which the component should read dimensions.
RECORD_INDEX	Specifies a common key used to identify records during join operations. RECORD_INDEX also specifies the property and dimension keys on which record sorts are validated.

Sub-element	Brief description
RECORD_JOIN	Describes how to perform a join.

Example

This example shows three sources being joined in a left join according to SID and ID keys.

```
<RECORD_ASSEMBLER NAME="ra-1" FRC_PVAL_IDX="TRUE">
  <RECORD_SOURCE>rs-1</RECORD_SOURCE>
  <RECORD_SOURCE>rs-2</RECORD_SOURCE>
  <RECORD_SOURCE>rs-3</RECORD_SOURCE>
  <RECORD_JOIN JOIN_TYPE="LEFT_JOIN">
    <JOIN_ENTRY>
      <RECORD_SOURCE>rs-1</RECORD_SOURCE>
      <KEY_DIMENSION TYPE="PVAL" ID="sid"/>
    </JOIN_ENTRY>
    <JOIN_ENTRY>
      <RECORD_SOURCE>rs-2</RECORD_SOURCE>
      <KEY_DIMENSION TYPE="PVAL" ID="id"/>
    </JOIN_ENTRY>
    <JOIN_ENTRY>
      <RECORD_SOURCE>rs-3</RECORD_SOURCE>
      <KEY_DIMENSION TYPE="PVAL" ID="id"/>
    </JOIN_ENTRY>
  </RECORD_JOIN>
</RECORD_ASSEMBLER>
```

RECORD_CACHE

A RECORD_CACHE element sorts records according to a specified RECORD_INDEX key and loads the records in a cache for join operations.

The cache itself consists of a combination of a system's available memory and a portion of its hard drive space. If Forge runs out of available memory for the cache, Forge allocates hard drive space as necessary to continue processing.

DTD

```
<!ELEMENT RECORD_CACHE
  ( COMMENT?
    , RECORD_SOURCE
    , DIMENSION_SOURCE?
    , RECORD_INDEX
  )
>
<!ATTLIST RECORD_CACHE
  NAME          CDATA          #REQUIRED
  FRC_PVAL_IDX  ( TRUE | FALSE )  "FALSE"
  DISK_BACKED   ( NONE | IN_MEMORY_INDEX ) "NONE"
  COMBINE_RECORDS ( TRUE | FALSE )  #IMPLIED
  MAX_RECORDS   CDATA          #IMPLIED
>
```

Attributes

The following sections describe the RECORD_CACHE element's attributes.

NAME

A unique name for the sort operation.

FRC_PVAL_IDX

Forces Forge to create a record or property index for better performance during processing. TRUE always creates an index during processing. FALSE allows Forge to determine when an index would improve performance and to create it at that time.

DISK_BACKED

This attribute is deprecated. Forge ignores any specified value.

COMBINE_RECORDS

Specifies whether to combine records from a single source if the records have the same key. During joins RECORD_CACHE combines records with the same RECORD_INDEX key. FALSE disables combining records. For more information about joining source data, see the *Endeca Forge Guide*.

MAX_RECORDS

This value specifies the how many records to load into the cache. Omitting this attribute loads all records.



Note: Use this attribute cautiously or you may get unexpected results during joins. For example, if you load only a small number of records, because you want faster processing in a testing environment, the record set may not be complete after sorting and joining. Therefore, some records may display incomplete results when navigated.

Sub-elements

The following table provides a brief overview of the RECORD_CACHE sub-elements.

Sub-element	Brief description
COMMENT	Associates a comment with a parent element and preserves the comment when the file is rewritten. This element provides an alternative to using inline XML comments of the form <!-- ... -->.
RECORD_SOURCE	Specifies the name of a pipeline component from which this component should read records.
DIMENSION_SOURCE	Specifies the name of a pipeline component from which the component should read dimensions.
RECORD_INDEX	Specifies the property and dimension keys on which record sorts are validated. Join operations also find records that share a common key based on the RECORD_INDEX element.

Example

This example loads 50,000 records based on the "ID" key.

```
<RECORD_CACHE COMBINE_RECORDS="TRUE" DISK_BACKED="NONE"
    FRC_PVAL_IDX="FALSE" MAX_RECORDS="50000" NAME="record-sort">
    <RECORD_SOURCE>LoadData</RECORD_SOURCE>
    <RECORD_INDEX UNIQUE="TRUE">
        <KEY_DIMENSION ID="ID" MIN_VALS="0" TYPE="PVAL" />
    </RECORD_INDEX>
</RECORD_CACHE>
```

RECORD_JOIN

A RECORD_JOIN element describes how to perform a join contained in a RECORD_ASSEMBLER element.

For more information about joining source data, see the *Endeca Forge Guide*.

DTD

```
<!ELEMENT RECORD_JOIN
  ( CONFIG*
  , JOIN_ENTRY+
  , WORK_ENTRY?
  )
>
<!ATTLIST RECORD_JOIN
  JOIN_TYPE      CDATA #REQUIRED
>
```

Attributes

The following section describes the RECORD_JOIN element's attribute.

JOIN_TYPE

Indicates the type of join you want the Data Foundry to perform. Valid values for JOIN_TYPE are: LEFT_JOIN, INNER_JOIN, COMBINE, OUTER_JOIN, SWITCH, SORT_SWITCH, DISJUNCT, FIRST_RECORD, and HISTORY_JOIN. See the *Endeca Forge Guide* for more detailed explanations about each type.

Sub-elements

The following table provides a brief overview of the RECORD_JOIN sub-elements.

Sub-element	Brief description
CONFIG	Provides generic parameterized configuration information.
RECORD_JOIN	Specifies the key used to join records.

Example

This example shows a snippet of three record sources being joined in a left join according to SID and ID keys.

```
<RECORD_JOIN JOIN_TYPE="LEFT_JOIN">
  <CONFIG NAME="UNIQUE_RECORD_PROPS" VALUE="FALSE" />
  <JOIN_ENTRY>
    <RECORD_SOURCE>rs-1</RECORD_SOURCE>
    <KEY_DIMENSION TYPE="PVAL" ID="sid"/>
  </JOIN_ENTRY>
  <JOIN_ENTRY>
    <RECORD_SOURCE>rs-2</RECORD_SOURCE>
    <KEY_DIMENSION TYPE="PVAL" ID="id"/>
  </JOIN_ENTRY>
  <JOIN_ENTRY>
    <RECORD_SOURCE>rs-3</RECORD_SOURCE>
    <KEY_DIMENSION TYPE="PVAL" ID="id"/>
```

```
</JOIN_ENTRY>
</RECORD_JOIN>
```

RECORD_MANIPULATOR

A RECORD_MANIPULATOR element contains EXPRESSION elements, which are evaluated against each record as Forge process it.

When an EXPRESSION is evaluated, it may modify the current record. The changes take a variety of forms depending on the expression, from adjusting property values to creating new data.



Note: Oracle recommends that you perform record manipulation with the PERL_MANIPULATOR element instead of the EXPRESSION and RECORD_MANIPULATOR elements.

DTD

```
<!ELEMENT RECORD_MANIPULATOR
  ( COMMENT?
    , RECORD_SOURCE
    , DIMENSION_SOURCE?
    , RECORD_INDEX?
    , PROP_DECL*
    , EXPRESSION*
  )
>
<!ATTLIST RECORD_MANIPULATOR
  NAME          CDATA          #REQUIRED
  FRC_PVAL_IDX  (TRUE | FALSE)  "TRUE"
>
```

Attributes

The following sections describe the RECORD_MANIPULATOR element's attributes.

NAME

Identifies the RECORD_MANIPULATOR so that it can be referenced by other components in Pipeline.epx.

FRC_PVAL_IDX

Forces Forge to create a record or property index for better performance during processing. TRUE always creates an index during processing. FALSE allows Forge to determine when an index would improve performance and to create it at that time.

Sub-elements

The following table provides a brief overview of the RECORD_MANIPULATOR sub-elements.

Sub-element	Brief description
COMMENT	Associates a comment with a parent element and preserves the comment when the file is rewritten. This element provides an alternative to using inline XML comments of the form <!-- ... -->.
RECORD_SOURCE	Specifies the name of a pipeline component from which this component should read records.

Sub-element	Brief description
DIMENSION_SOURCE	Specifies the name of a pipeline component from which the component should read dimensions.
RECORD_INDEX	Specifies the property and dimension keys on which record sorts are validated. Join operations also find records that share a common key based on the RECORD_INDEX element.
EXPRESSION	Instructs Forge about how to modify data in the pipeline.

RECORD_SOURCE

A RECORD_SOURCE element specifies the name of a pipeline component from which a component should read records.

Using the name reference, RECORD_SOURCE connects components that act on records being processed (for example, RECORD_ADAPTER, RECORD_MANIPULATOR, JAVA_MANIPULATOR, and so on).

DTD

```
<!ELEMENT RECORD_SOURCE (#PCDATA)>
```

Attributes

The RECORD_SOURCE element has no attributes.

Sub-elements

The RECORD_SOURCE element has no sub-elements.

Example

This example shows an indexer adapter that indexes source records from the RecordManipulator Adapter.

```
<INDEXER_ADAPTER NAME="IndexerAdapter"
  OUTPUT_URL="..../partition0/forge_output/"
  FRC_PVAL_IDX="TRUE" OUTPUT_PREFIX="wine"
  OUTPUT_RECORD_FORMAT="BINARY"
  OUTPUT_DIMENSION_FORMAT="INTERNAL_DIM_XML">
  <RECORD_SOURCE>RecordManipulator</RECORD_SOURCE>
  <DIMENSION_SOURCE>DimensionServer</DIMENSION_SOURCE>
</INDEXER_ADAPTER>
```

ROLLOVER

A ROLLOVER element controls the point at which Forge rolls over record output to a new file.

For example, when Forge writes a large amount of records to a single file, you can set TYPE, CUTOFF, and ROLL_URL to create another file for additional record storage.

ROLLOVER also controls which Dgidx (indexer) processes records. In cases where multiple Forge instances process records, you can control which records are sent to a particular Dgidx instance with the NUM_IDX, PROP_NAME, PROP_TYPE, REMOVE_PROP, and VALIDATE attributes. This

capability is useful when you want to send records to a specific Dgidx based on a particular PROP_NAME.

DTD

```
<!ELEMENT ROLLOVER EMPTY>
<!ATTLIST ROLLOVER
  NAME          CDATA          #REQUIRED
  NUM_IDX       CDATA          #IMPLIED
  PROP_NAME     CDATA          #IMPLIED
  PROP_TYPE     (ALPHA | INTEGER) "ALPHA"
  REMOVE_PROP   (TRUE | FALSE)  "FALSE"
  VALIDATE     (TRUE | FALSE)  "FALSE"
  TYPE          (SIZE | ENTRIES) #IMPLIED
  CUTOFF        CDATA          #IMPLIED
  ROLL_URL      CDATA          #IMPLIED
>
```

Attributes

The following sections describe the ROLLOVER element's attributes.

NAME

Identifies the type of the ROLLOVER element. NAME should be set to NAME="RECORD".

NUM_IDX

Identifies the number of Dgidx instances available to Forge. This number corresponds to the number of Dgraphs, which in turn corresponds to the number of file sets Forge creates. For example, if NUM_IDX="3" then there are three Dgidx instances, each with its own file set for record processing and its own Dgraph accessing that file set.

PROP_NAME

Indicates the name of the property by which Forge assigns records to a Dgidx instance defined in NUM_IDX. For example, if you provide PROP_NAME="SSN", Forge assigns all records with the SSN property to one Dgidx, and consequently those records are accessed by a single Dgraph.

PROP_TYPE

Indicates the property type of PROP_NAME. Valid values are ALPHA and INTEGER. The default is ALPHA. Use INTEGER if you know exactly which Dgidx you want to process records. Use ALPHA if you are employing roll-up capabilities in your application's user interface and then send the correct roll-up records to the appropriate Dgidx.

REMOVE_PROP

Removes the PROP_NAME used to determine record processing. The default value is FALSE.

VALIDATE

Validates that all records are checked for the presence of multiple values of PROP_NAME. A warning is logged for each record with multiple values.

TYPE

Identifies the type of measure for the CUTOFF attribute. The valid values are SIZE (which is measured in bytes) or ENTRIES (which is an integer).

CUTOFF

Describes the cutoff threshold after which Forge generates a new file. This value is expressed as either the number of bytes (the SIZE attribute) or an integer representing the number of record entries (the ENTRIES attribute).

When creating a new file once the CUTOFF threshold has been reached, Forge generates filenames that follow this format:

```
{prefix}[-part#][-segment#].records.{format}[.gz]
```

where each section is created only as needed. The -part# is used for indexer and -segment# is used for size, so the same part number and different segment numbers indicates the data is part of the same file set.

ROLL_URL

This attribute is deprecated. The new output file is created in the directory specified by the adapter's OUTPUT_URL attribute. The new file name conforms to the syntax listed above in the CUTOFF attribute.

Sub-elements

The ROLLOVER element has no sub-elements.

Example

This example shows a ROLLOVER element that creates a new file when the number of records processed exceeds 20,000 records (based on the ENTRIES attribute). Records are assigned to one of three indexers based on the PROP1 property.

```
<ROLLOVER CUTOFF="20000" NAME="RECORD" NUM_IDX="3"
  PROP_NAME="PROP1" PROP_TYPE="ALPHA" REMOVE_PROP="FALSE"
  ROLL_URL=" " TYPE="ENTRIES" VALIDATE="FALSE" />
```

TRANSFORMER

A TRANSFORMER element instructs Forge to transform .xml from an external source into Endeca-compatible .xml according to a specified .xsl style sheet. The TRANSFORMER element may be used as a sub-element of either DIMENSION_ADAPTER or RECORD_ADAPTER. Therefore it can be used to transform either external dimensions or external source data into Endeca-compatible .xml for dimensions or records.

When included within a DIMENSION_ADAPTER element, the TRANSFORMER transforms a dimension hierarchy from an external taxonomy into Endeca dimensions. Because the structure of a data hierarchy varies widely, Endeca does not provide an .xsl style sheet to transform company-specific data sets with the exception of external taxonomies from Stratify. For Stratify, Endeca provides an .xsl file. For other dimension hierarchies, you can write an .xsl file that instructs Forge how to transform your source elements into elements that conform to Endeca .xml as defined in external_dimensions.dtd. The external_dimensions.dtd file can be found in %ENDECA_ROOT%\conf\dtd on Windows and \$ENDECA_ROOT/conf/dtd on UNIX.

When included within a RECORD_ADAPTER element, the TRANSFORMER transforms .xml source data into Endeca records. For external source data, you can write an .xsl file that instructs Forge how to transform your source elements into elements that conform to Endeca .xml as defined in records.dtd. The records.dtd file can be found in %ENDECA_ROOT%\conf\dtd on Windows and \$ENDECA_ROOT/conf/dtd on UNIX.

DTD

```
<!ELEMENT TRANSFORMER EMPTY>
<!ATTLIST TRANSFORMER
  TYPE      CDATA      #REQUIRED
  URL       CDATA      #REQUIRED
  >
```

Attributes

The following section describes the TRANSFORMER element's attributes.

TYPE

Identifies the file format of the transformation style sheet. The only valid value is XSLT.

URL

Specifies the location of the .xsl file. The path is either an absolute path or a path relative to the location of the Pipeline.epx file. With an absolute path, the protocol must be specified in RFC 2396 syntax. Usually this means the prefix `file:///` precedes the path to the data file. Relative URLs must not specify the protocol and are relative to the URL used to locate the Pipeline.epx file.

For a Stratify taxonomy, this URL is populated by default with the .xsl that Endeca provides.

Sub-elements

The TRANSFORMER element has no sub-elements.

Example

This example shows a dimension adapter reading in a Stratify taxonomy and transforming it using the `stratify2extdim.xsl` stylesheet.

```
<DIMENSION_ADAPTER DIRECTION="INPUT" FORMAT="STRATIFY"
  NAME="Dimensions" URL="ask_alice_dimensions.xml">
  <TRANSFORMER TYPE="XSLT" URL="stratify2extdim.xsl" />
</DIMENSION_ADAPTER>
```

UPDATE_ADAPTER

As part of a partial update Pipeline.epx, an UPDATE_ADAPTER element writes partial update information for a running Endeca MDEX Engine to perform a live update.

An update adapter is typically the last component of a partial update Pipeline.epx file. See the *Endeca Partial Updates Guide* for additional details.

DTD

```
<!ELEMENT UPDATE_ADAPTER
  ( COMMENT? ,
    RECORD_SOURCE ,
    DIMENSION_SOURCE* ,
    RECORD_ID_SPEC? ,
    ROLLOVER?
  )
>
<!ATTLIST UPDATE_ADAPTER
  NAME      CDATA      #REQUIRED
  OUTPUT_URL CDATA      #REQUIRED
  >
```

```

  OUTPUT_PREFIX      CDATA      #IMPLIED
  MULTI             ( TRUE | FALSE ) #IMPLIED
  MULTI_PROP_NAME   CDATA      #IMPLIED
  FILTER_UNKNOWN_PROPS ( TRUE | FALSE ) "TRUE"
  %compression;
>

```

Attributes

The following section describes the UPDATE_ADAPTER element's attributes.

NAME

Identifies the UPDATE_ADAPTER so that it can be referenced by other pipeline components.

OUTPUT_URL

Identifies the directory to which Forge writes its files and processed records. The path is either an absolute path or a path relative to the location of the Pipeline.epx file. With an absolute path, the protocol must be specified in RFC 2396 syntax. Usually this means the prefix `file:///` precedes the path to the data file. Relative URLs must not specify the protocol and are relative to the URL used to locate the Pipeline.epx file.

OUTPUT_PREFIX

Specifies the filename prefix to add when Forge writes its output files. The default is `out`.

MULTI

When used in an INPUT adapter, the MULTI attribute specifies whether Forge can read data from more than one input file. The default, FALSE, indicates that the URL is a single input file. If set to TRUE, the input URL is interpreted as a pattern, and Forge reads each file matching the pattern in sequence. For example, the adapter may specify a URL pattern of `*.update`, in which case Forge reads any file in the given directory that has the `.update` suffix. This value must be set to TRUE if you want to use MULTI_PROP_NAME.

When used in an OUTPUT adapter, the MULTI and MULTI_PROP_NAME attributes specify which file each record is written to. If MULTI="TRUE" then Forge checks MULTI_PROP_NAME for the location.

MULTI_PROP_NAME

Specifies a property name that indicates the location that a record coming through Forge should be written to. (Forge stores a property on each record that is the source URL for that record.) Setting this property is useful if you want to process multiple input files and also keep the output distinct. In such cases, set MULTI="TRUE" and then set MULTI_PROP_NAME="propname" to specify the location that the given record coming through Forge should be written to.

For example, suppose you have an input files named `datedfile#1.txt` and `datedfile#2.txt` that are unique based on the date in the file name. Further suppose you set MULTI="TRUE", set MULTI_PROP_NAME="Absolute_url", and set OUTPUT_PREFIX="out" in an OUTPUT adapter. Forge processes the files from the `Absolute_url` value of the input directory and file name, and Forge writes `out.datedfile#1.records.xml` and `out.datedfile#2.records.xml` to the OUTPUT_URL. The output files contain only the processed records from their corresponding input files.

FILTER_UNKNOWN_PROPS

Specifies whether unmapped properties should be removed from the processed records. The default value is TRUE. The value in a partial update pipeline should be the same as in the baseline pipeline.

COMPRESSION_LEVEL

Controls the level of data compression when writing data. The default compression level for this attribute is 0 (no compression). The value "-1" for this attribute has been deprecated. Values 1-9 indicate increasing levels of compression.

Sub-elements

The following table provides a brief overview of the UPDATE_ADAPTER sub-elements.

Sub-element	Brief description
COMMENT	Associates a comment with a parent element and preserves the comment when the file is rewritten. This element provides an alternative to using inline XML comments of the form <!-- ... -->.
RECORD_SOURCE	Specifies the name of a pipeline component from which this component should read records.
DIMENSION_SOURCE	Specifies the name of a pipeline component from which the component should read dimensions.
ROLLOVER	Controls the point at which record output gets rolled over to a new file, and which Dgidx (indexer) processes records.

Example

This example shows a simple update adapter.

```
<UPDATE_ADAPTER NAME="UpdateOutput" OUTPUT_PREFIX="update"
    OUTPUT_URL=".../data/partition0/forge_output/"
    FILTER_UNKNOWN_PROPS="TRUE">
    <RECORD_SOURCE>RecordManipulator</RECORD_SOURCE>
    <DIMENSION_SOURCE>DimensionServer</DIMENSION_SOURCE>
</UPDATE_ADAPTER>
```

Precedence_rules.xml elements

The precedence_rules.xml file contains the precedence rules for your application.

Precedence rules allow your application to delay dimension display until the user triggers the display. In other words, precedence rules are triggers that cause dimensions that were not previously displayed to now be available. This makes navigation through the data easier, and is essential to avoid information overload problems.

PRECEDENCE_RULE

The PRECEDENCE_RULE element allows your application to delay dimension display until the user triggers the display.

Precedence rules are triggers that cause dimensions that were not previously displayed to now be available. This makes navigation through the data easier and is essential to avoid information overload problems.

For example, one might not want both the "Country" and "State" dimensions to appear simultaneously in a geographical data set. A PRECEDENCE_RULE could be defined so that the "State" dimension appears only after a dimension value from the "Country" dimension is selected. In this example, Country

would correspond to the source dimension value and State would correspond to the destination dimension value.

DTD

```
<!ELEMENT PRECEDENCE_RULE EMPTY>
<!ATTLIST PRECEDENCE_RULE
  TYPE          ( STANDARD | LEAF )      #REQUIRED
  SRC_DVAL_ID   CDATA                  #REQUIRED
  DEST_DVAL_ID  CDATA                  #REQUIRED
>
```

Attributes

The following section describes the PRECEDENCE_RULE element's attributes.

TYPE

The type of source dimension value for a PRECEDENCE_RULE. There are two possible values: STANDARD and LEAF.

- STANDARD means that if the dimension value specified as the trigger or any of its descendants are in the navigation state, then the target is presented (one trigger, one target).
- LEAF means that querying any leaf dimension value from the trigger dimension will cause the target dimension value to be displayed (many triggers, one target).

SRC_DVAL_ID

Specifies the source dimension value that must be selected before the user can see the destination dimension value (DEST_DVAL_ID).

DEST_DVAL_ID

Specifies the destination dimension value that appears after the source dimension value is selected.

Sub-elements

PRECEDENCE_RULE contains no sub-elements.

Example

This example shows a STANDARD-type precedence rule taken from the wine reference.

```
<PRECEDENCE_RULES>
  <PRECEDENCE_RULE DEST_DVAL_ID="11" SRC_DVAL_ID="8" TYPE="STANDARD" />
</PRECEDENCE_RULES>
```

PRECEDENCE_RULES

A PRECEDENCE_RULES element specifies the individual precedences rules available to your pipeline.

Each precedence rule is represented by an individual PRECEDENCE_RULE element.

DTD

```
<!ELEMENT PRECEDENCE_RULES
  ( COMMENT?
    , PRECEDENCE_RULE*
  )
>
```

Attributes

The PRECEDENCE_RULES element has no attributes.

Sub-elements

The following table provides a brief overview of the PRECEDENCE_RULES sub-elements.

Sub-element	Brief description
COMMENT	Associates a comment with a parent element and preserves the comment when the file is rewritten. This element provides an alternative to using inline XML comments of the form <!-- ... -->.
PRECEDENCE_RULE	Allows your application to delay dimension display until the user triggers the display.

Example

This example shows a STANDARD-type precedence rule taken from the wine reference.

```
<PRECEDENCE_RULES>
  <PRECEDENCE_RULE DEST_DVAL_ID="11" SRC_DVAL_ID="8" TYPE="STANDARD" />
</PRECEDENCE_RULES>
```

Profiles.xml elements

The Profiles.xml file contains a PROFILE element for every user profile in your project.

PROFILE elements are grouped in the PROFILES root element.

PROFILES

A PROFILES element contains any number of PROFILE elements to indicate a user type or user group.

Each profile is represented by an individual PROFILE element, which is an element in the Common.dtd file.

DTD

```
<!ELEMENT PROFILES
  ( COMMENT?
    , PROFILE*
  )
>
```

Attributes

The PROFILES element has no attributes.

Sub-elements

The following table provides a brief overview of the PROFILES sub-elements.

Sub-element	Brief description
COMMENT	Associates a comment with a parent element and preserves the comment when the file is rewritten. This element provides an alternative to using inline XML comments of the form <!-- ... -->.
PROFILE	Specifies a user type or user group. Profiles are used as a type of dynamic business rule trigger.

Example

This example identifies a user type named premium_subscriber.

```
<PROFILES>
  <PROFILE>premium_subscriber</PROFILE>
</PROFILES>
```

Project.xml elements

The Project.xml file points to all of the files that are input to Forge and Dgidx.

The project files include dimensions.xml and the index configuration files. You do not typically need to edit this file.

DIMENSION_INPUTS

The DIMENSION_INPUTS element identifies the dimensions.xml file used to define the project.

DTD

```
<!ELEMENT DIMENSION_INPUTS
  ( INPUT+
  )
>
```

Attributes

The DIMENSION_INPUTS element has no attributes.

Sub-elements

The following table provides a brief overview of the RECORD_INPUTS sub-element.

Sub-element	Brief description
INPUT	Provides details about the specified file.

Example

The following example defines a wine project.

```
<PROJECT NAME="wine">
  <DIMENSION_INPUTS>
    <INPUT FORMAT="XML" URL="wine.dimensions.xml" />
  </DIMENSION_INPUTS>
```

```
<RECORD_INPUTS>
  <INPUT FORMAT="BINARY" NUM_PARTITIONS="1" PARTITION="0"
        SEGMENT="0" URL="wine.records.binary" />
</RECORD_INPUTS>
</PROJECT>
```

INPUT

The INPUT element provides specific information about files listed in the PROJECT element.

DTD

```
<!ELEMENT INPUT EMPTY>
<!ATTLIST INPUT
  FORMAT          CDATA    #REQUIRED
  URL             CDATA    #REQUIRED
  NUM_PARTITIONS  CDATA    #REQUIRED
  PARTITION       CDATA    #IMPLIED
  SEGMENT         CDATA    #IMPLIED
  >
```

Attributes

The following section describes the INPUT element's attributes.

FORMAT

The format of the data in the file. Depending on the file type, the value can be XML or BINARY.

URL

Path to the file, with a prefix matching the project name.

NUM_PARTITIONS

For RECORD_INPUTS, the number of partitions.

PARTITION

For RECORD_INPUTS, specifies the location of a portion of the data. This attribute is used when there are multiple Dgraphs.

SEGMENT

For RECORD_INPUTS, when rollover is turned TRUE, each partition may be further divided into multiple segments. A SEGMENT element specifies the location of one of these segments.

Sub-elements

The INPUT element has no sub-elements.

Example

The following example defines a wine project.

```
<PROJECT NAME="wine">
  <DIMENSION_INPUTS>
    <INPUT FORMAT="XML" URL="wine.dimensions.xml" />
  </DIMENSION_INPUTS>
  <RECORD_INPUTS>
    <INPUT FORMAT="BINARY" NUM_PARTITIONS="1" PARTITION="0"
          SEGMENT="0" URL="wine.records.binary" />
  </RECORD_INPUTS>
</PROJECT>
```

```
</RECORD_INPUTS>
</PROJECT>
```

PROJECT

The PROJECT element defines all of the elements in a project.

DTD

```
<!ELEMENT PROJECT
  ( DIMENSION_INPUTS?
  , RECORD_INPUTS?
  )
>
<!ATTLIST PROJECT
  NAME      CDATA      #REQUIRED
>
```

Attributes

The following section describes the PROJECT element's attribute.

NAME

A unique name for this project.

Sub-elements

The following table provides a brief overview of the PROJECT sub-elements.

Sub-element	Brief description
DIMENSION_INPUTS	Path to the dimensions.xml file for the project.
RECORD_INPUTS	Path to and information about the record source for the project.

Example

The following example defines a wine project.

```
<PROJECT NAME="wine">
  <DIMENSION_INPUTS>
    <INPUT FORMAT="XML" URL="wine.dimensions.xml" />
  </DIMENSION_INPUTS>
  <RECORD_INPUTS>
    <INPUT FORMAT="BINARY" NUM_PARTITIONSS="1" PARTITION="0"
          SEGMENT="0" URL="wine.records.binary" />
  </RECORD_INPUTS>
</PROJECT>
```

RECORD_INPUTS

The RECORD_INPUTS element identifies and describes the file used to import records into the project.

DTD

```
<!ELEMENT RECORD_INPUTS
  ( INPUT+
```

```
    )  
>
```

Attributes

The RECORD_INPUTS element has no attributes.

Sub-elements

The following table provides a brief overview of the RECORD_INPUTS sub-element.

Sub-element	Brief description
INPUT	Provides details about the specified file.

Example

The following example defines a wine project.

```
<PROJECT NAME="wine">  
  <DIMENSION_INPUTS>  
    <INPUT FORMAT="XML" URL="wine.dimensions.xml"/>  
  </DIMENSION_INPUTS>  
  <RECORD_INPUTS>  
    <INPUT FORMAT="BINARY" NUM_PARTITIONS="1" PARTITION="0"  
          SEGMENT="0" URL="wine.records.binary"/>  
  </RECORD_INPUTS>  
</PROJECT>
```

Prop_refs.xml elements

The Prop_refs.xml file contains a PROP_REF element for every property in your pipeline.

The PROP_REF element indicates the name and data type of each property. PROP_REF elements are grouped in the PROP_REFS root element.

PROP_REF

The PROP_REF element specifies the name and data type of properties in your pipeline.

DTD

```
<!ELEMENT PROP_REF EMPTY>  
<!ATTLIST PROP_REF  
  NAME      CDATA          #REQUIRED  
  TYPE      ( ALPHA  
            | INTEGER  
            | DOUBLE  
            | FIXEDPOINT  
            | FILE_PATH  
            | GEOFENCE  
            | DATETIME  
            | DURATION  
            | TIME )          #REQUIRED  
>
```

Attributes

The following sections describe the PROP_REF element's attributes.

NAME

The unique identifier for this property.

TYPE

Indicates the data type of this property:

- ALPHA - used for alphanumeric data.
- INTEGER - used for integer data.
- DOUBLE - used for floating point data.
- FIXEDPOINT - not supported.
- FILE_PATH - deprecated.
- GEOCODE - a pair of double precision floating point values representing a latitude and longitude pair. Used for geospatial filtering and sorting.
- DATETIME - used for values that represent a time of the day on a given date.
- DURATION - used for lengths of time; intended for use with Endeca Analytics.
- TIME - used for the time of day; intended for use with Endeca Analytics.

Sub-elements

The PROP_REF element has no sub-elements.

Example

This example shows some of the properties defined in a project.

```
<PROP_REFS>
  <PROP_REF NAME="P_Body" TYPE="ALPHA" />
  <PROP_REF NAME="P_Description" TYPE="ALPHA" />
  <PROP_REF NAME="P_Price" TYPE="DOUBLE" />
  <PROP_REF NAME="P_Year" TYPE="INTEGER" />
  <PROP_REF NAME="Location" TYPE="GEOCODE" />
  ...others deleted for simplicity...
</PROP_REFS>
```

PROP_REFS

A PROP_REFS element contains the properties specified for your pipeline.

Each individual property is specified in a PROP_REF element.

DTD

```
<!ELEMENT PROP_REFS
  ( COMMENT?
    , PROP_REF*
  )
>
```

Attributes

The PROP_REFS element has no attributes.

Sub-elements

The following table provides a brief overview of the PROP_REFs sub-elements.

Sub-element	Brief description
COMMENT	Associates a comment with a parent element and preserves the comment when the file is rewritten. This element provides an alternative to using inline XML comments of the form <!-- ... -->.
PROP_REF	Specifies the name and data type of properties in your pipeline.

Example

This example shows some of the properties defined in a project.

```
<PROP_REFs>
  <PROP_REF NAME="P_Body" TYPE="ALPHA" />
  <PROP_REF NAME="P_Description" TYPE="ALPHA" />
  <PROP_REF NAME="P_Price" TYPE="DOUBLE" />
  <PROP_REF NAME="P_Year" TYPE="INTEGER" />
  <PROP_REF NAME="Location" TYPE="GEOCODE" />
  ...others deleted for simplicity...
</PROP_REFs>
```

Record_filter.xml elements

The Record_filter.xml file specifies the properties enabled for a custom catalog filter.

Each property is indicated by a RECORD_FILTER element. See the "Record Filters" chapter in the *Endeca Advanced Development Guide* for details.

RECORD_FILTER

A RECORD_FILTER element adds the specified property to a custom catalog filter.

Custom catalog filters present a subset of the data to the end-user. See the "Record Filters" chapter in the *Endeca MDEX Engine Advanced Development Guide* for details.

DTD

```
<!ELEMENT RECORD_FILTER
  ( COMMENT?
    , PROPNAMES*
  )
>
```

Attributes

The RECORD_FILTER element has no attributes.

Sub-elements

The following table provides a brief overview of the RECORD_FILTER sub-elements.

Sub-element	Brief description
COMMENT	Associates a comment with a parent element and preserves the comment when the file is rewritten. This element provides an alternative to using inline XML comments of the form <!-- ... -->.
PROPNAM	Represents a property.

Example

This example adds an access control list property to the records being processed.

```
<RECORD_FILTER>
  <PROPNAM>Endeca.AC.L.Allow.Read</PROPNAM>
</RECORD_FILTER>
```

Record_id_prop.xml elements

The Record_id_prop.xml file contains a RECORD_ID_PROP element that specifies a property to identify records during partial updates.

When implementing partial updates, the RECORD_ID_PROP element uses this property to preserve stable record IDs across baseline runs. That is, a record will have the same ID in the next update as in the current update.

RECORD_ID_PROP

A RECORD_ID_PROP element indicates that this property should be used as the record ID to identify records.

If a property is to be used as a record ID, it must fulfill the following criteria:

- It must be a 32-bit unsigned integer.
- The value of this property must be unique for each record.
- No more than one property may be specified by the sub-element PROPNAM.



Note: This element is very similar to RECORD_SPEC which also identifies records during updates. The difference is that the value of PROPNAM in RECORD_ID_PROP must be an integer; whereas, the value of PROPNAM in RECORD_SPEC can be a string.

DTD

```
<!ELEMENT RECORD_ID_PROP
  ( COMMENT?
    , PROPNAM?
  )
>
```

Attributes

The RECORD_ID_PROP element has no attributes.

Sub-elements

The following table provides a brief overview of the RECORD_ID_PROP sub-elements.

Sub-element	Brief description
COMMENT	Associates a comment with a parent element and preserves the comment when the file is rewritten. This element provides an alternative to using inline XML comments of the form <!-- ... -->.
PROPNAM	Represents the property to be used as a record ID.

Example

This example identifies records by their RecordIdProp property.

```
<RECORD_ID_PROP>
  <PROPNAM>RecordIdProp</PROPNAM>
</RECORD_ID_PROP>
```

Record_sort_config.xml elements

The Record_sort_config.xml file specifies properties or dimensions that users can sort by in an application.

The root element RECORD_SORT_CONFIG contains a list of properties or dimensions users can sort by. Each property or dimension is specified in a RECORD_SORT element.

RECORD_SORT

A RECORD_SORT element specifies whether the MDEX Engine uses precomputed sort on this property or dimension, to optimize sort processing.

DTD

```
<!ELEMENT RECORD_SORT EMPTY>
<!ATTLIST RECORD_SORT
  NAME      CDATA      #REQUIRED
>
```

Attributes

The following sections describe the RECORD_SORT element's attributes.

NAME

Specifies the name of the property or dimension on which the MDEX Engine uses precomputed sort, to optimize processing.

Sub-elements

The RECORD_SORT element has no sub-elements.

Example

This example shows three properties that the MDEX Engine uses for precomputed sort:

```
<RECORD_SORT_CONFIG>
  <RECORD_SORT NAME="Name" />
  <RECORD_SORT NAME="P_PriceStr" />
  <RECORD_SORT NAME="P_Year" />
</RECORD_SORT_CONFIG>
```

RECORD_SORT_CONFIG

A RECORD_SORT_CONFIG element enables precomputed sort by the MDEX Engine, according to specified properties or dimensions in an application.

Within the RECORD_SORT_CONFIG element, each property or dimension that you want to enable for precomputed sorting should be specified in a RECORD_SORT sub-element.

DTD

```
<!ELEMENT RECORD_SORT_CONFIG
  ( COMMENT?
    , RECORD_SORT*
  )
>
```

Attributes

The RECORD_SORT_CONFIG element has no attributes.

Sub-elements

The following table provides a brief overview of the RECORD_SORT_CONFIG sub-elements.

Sub-element	Brief description
COMMENT	Associates a comment with a parent element and preserves the comment when the file is rewritten. This element provides an alternative to using inline XML comments of the form <!-- ... -->.
RECORD_SORT	Specifies a property or dimension on which the MDEX Engine uses precomputed sort, to optimize processing.

Example

This example shows three properties in an application for which the MDEX Engine uses precomputed sort:

```
<RECORD_SORT_CONFIG>
  <RECORD_SORT NAME="Name" />
  <RECORD_SORT NAME="P_PriceStr" />
  <RECORD_SORT NAME="P_Year" />
</RECORD_SORT_CONFIG>
```

Record_spec.xml element

The Record_spec.xml file contains a RECORD_SPEC element that specifies a property to identify records during partial updates.

When implementing partial updates, the RECORD_SPEC element uses this property to preserve stable record IDs across baseline runs. That is, a record will have the same ID in the next update as in the current update. For more information, see the *Endeca MDEX Engine Partial Updates Guide*.

RECORD_SPEC

A RECORD_SPEC element specifies that this property should be used as the record specification to identify records during partial updates.

If a property is to be used as a record specification property, it must fulfill the following criteria:

- Every record must have exactly one assignment of this property.
- The value of this property must be unique for each record.
- No more than one property is identified by the PROPNAMEx sub-element.



Note: This element is very similar to RECORD_ID_PROP which also identifies records during partial updates. The difference is that the value of PROPNAMEx in RECORD_ID_PROP must be an integer; whereas, the value of PROPNAMEx in RECORD_SPEC can be a string.

DTD

```
<!ELEMENT RECORD_SPEC
  ( COMMENT?
    , PROPNAMEx?
  )
>
```

Attributes

The RECORD_SPEC element has no attributes.

Sub-elements

The following table provides a brief overview of the RECORD_SPEC sub-elements.

Sub-element	Brief description
COMMENT	Associates a comment with a parent element and preserves the comment when the file is rewritten. This element provides an alternative to using inline XML comments of the form <!-- ... -->.
PROPNAMEx	Specifies the property to be used as the record specification property.

Example

This example sets the identifies records to update by the SKU_ID property.

```
<RECORD_SPEC>
  <PROPNAMEx>SKU_ID</PROPNAMEx>
</RECORD_SPEC>
```

Recsearch_config.xml elements

The Recsearch_config.xml configures record search.

In the file's RECSEARCH_CONFIG root element, you can also configure Did You Mean and automatic spelling correction options for dimension search. For more information about spelling corrections, see "Using Spelling Correction and Did You Mean" in the *Endeca Advanced Development Guide*.

RECSEARCH_CONFIG

A RECSEARCH_CONFIG element sets up the configuration of dimensions for dimension searches.

Dimension searches search against the text collection that consists of the names of all the dimension values in the data set.



Note: Do not modify the `ENABLE_AUTO_SUGGEST` and `ENABLE_DID_YOU_MEAN` attributes for this element, since they are no longer supported starting with the MDEX Engine 6.1.0. To configure Did You Mean and automatic spelling correction options, you must use the corresponding flags for the Dgraph. For more information about spelling corrections, see "Using Spelling Correction and Did You Mean" in the *Endeca MDEX Engine Advanced Development Guide*.

DTD

```
<!ELEMENT RECSEARCH_CONFIG
  ( COMMENT?
  , DID_YOU_MEAN?
  , AUTO_SUGGEST?
  , SEARCH_INTERFACE*
  )
>
<!ATTLIST RECSEARCH_CONFIG
  WHY_MATCH          (NONE | CONCISE | COMPLETE)  "NONE"
  WORD_INTERP        ( TRUE  | FALSE )           "FALSE"
  RETURN_RELRANK_SCORE ( TRUE  | FALSE )           "FALSE"
  ENABLE_DID_YOU_MEAN ( TRUE  | FALSE )           "#IMPLIED"
  ENABLE_AUTO_SUGGEST ( TRUE  | FALSE )           "#IMPLIED"
>
```

Attributes

The following sections describe the RECSEARCH_CONFIG element's attributes.

WHY_MATCH

When set to COMPLETE, this attribute specifies whether to enable computation of "Why Did It Match" attributes returned with full text search queries. These dynamic attributes contain a copy of the property/dimension key and value that caused the match along with query interpretation notes (spelling, thesaurus, etc.).

When set to CONCISE, this attribute produces more concise dynamic attribute values containing only the property/dimension key and query interpretation notes. This is useful when a property value might include large amounts of text, such as document contents.

When set to NONE, this feature is disabled. The default value is NONE.

WORD_INTERP

Specifies whether to enable word interpretation forms (see-also suggestions) of user query terms considered by the text search engine while processing record search requests. The default value is FALSE.

RETURN_RELRANK_SCORE

Specifies whether to return dimension value attributes that indicate the relevance rank score for dimension search results. The default value is FALSE.

ENABLE DID YOU MEAN



Note: Do not change the value for this attribute in the file. The Dgraph ignores the changed value starting with the MDEX Engine v.6.1.0. Instead, enable "Did you mean" with the --dym flag for the Dgraph.

Specifies whether the application should return explicit alternatives for search terms as a part of spelling correction. TRUE enables Did You Mean suggestions. FALSE disables them. Use the DID_YOU_MEAN sub-element to configure Did You Mean suggestions.

ENABLE_AUTO_SUGGEST



Note: Do not change the value for this attribute in the file. The Dgraph ignores the changed value starting with the MDEX Engine v.6.1.0. Instead, enable automatic correction with the --spl flag for the Dgraph.

Specifies whether automatic spelling correction is enabled for record searches. TRUE enables automatic spelling correction. FALSE disables it. Use the AUTO_SUGGEST sub-element to configure automatic spelling corrections.

Sub-elements

The following table provides a brief overview of the RESEARCH_CONFIG sub-elements.

Sub-element	Brief description
COMMENT	Associates a comment with a parent element and preserves the comment when the file is rewritten. This element provides an alternative to using inline XML comments of the form <!-- ... -->.
DID_YOU_MEAN	Specifies how to configure explicit alternatives for search terms as a part of spelling correction.
AUTO_SUGGEST	Specifies how to configure automatic spelling correction for either record searches or dimension searches.
SEARCH_INTERFACE	Represents a named collection of dimensions and/or properties.

Example

This example shows the configuration for the wine reference implementation.

```
<RESEARCH_CONFIG>
  <SEARCH_INTERFACE CROSS_FIELD_BOUNDARY="NEVER"
    CROSS_FIELD_RELEVANCE_RANK="0"
    DEFAULT_RELRANK_STRATEGY="All" NAME="All">
    <MEMBER_NAME RELEVANCE_RANK="4">P_WineType</MEMBER_NAME>
    <MEMBER_NAME RELEVANCE_RANK="3">P_Name</MEMBER_NAME>
    <MEMBER_NAME RELEVANCE_RANK="2">P_Winery</MEMBER_NAME>
```

```

<MEMBER_NAME RELEVANCE_RANK="1">P_Description</MEMBER_NAME>
</SEARCH_INTERFACE>
</RECREARCH_CONFIG>

```

Recsearch_indexes.xml elements

The Recsearch_indexes.xml file enables specified properties and dimensions for record searching.

Record search finds all records in an Endeca application that have a property or dimension whose value matches a term the user provides. The RECSEARCH_INDEX element specifies each property or dimension and indicates whether to consider ancestor dimension values when matching a dimension search query. RECSEARCH_INDEX elements are grouped in the RECSEARCH_INDEXES parent element.

RECSEARCH_INDEX

A RECSEARCH_INDEX element enables a property or dimension for record search.

DTD

```

<!ELEMENT RECSEARCH_INDEX ( SEARCH_INDEX )>
<!ATTLIST RECSEARCH_INDEX
      NAME          CDATA          #REQUIRED
      RECSEARCH_HIERARCHY ( TRUE | FALSE )  " FALSE "
>

```

Attributes

The following sections describe the RECSEARCH_INDEX element's attributes.

NAME

Specifies the dimension or property name that you want to enable for record search.

RECSEARCH_HIERARCHY

This attribute is used for dimensions. When set to TRUE, RECSEARCH_HIERARCHY specifies that a record search on dimension values from this dimension should match against words in the entire set of dimension values in the hierarchy rather than match only against one dimension value. For example, if a dimension value hierarchy is Electronics > Computers > Desktop PCs, then a record search on the Electronics dimension for "desktop computers" returns records associated with Desktop PCs because "desktop" matches the leaf and "computers" matches its parent. Although the two words occur in distinct dimension values, the leaf records are returned because the entire hierarchy is searched.

When set to FALSE, RECSEARCH_HIERARCHY specifies that a record search on dimension values from this dimension may not match against words in the entire set of dimension values in the hierarchy. For example, if a dimension value hierarchy is Electronics > Computers > Desktop PCs, then a record search on the Electronics dimension for "desktop computers" returns no records because the matches for "desktop" and "computers" span multiple dimensions in the hierarchy. The default value is FALSE.

Sub-elements

The following table provides a brief overview of the RECSEARCH_INDEX sub-elements.

Sub-element	Brief description
SEARCH_INDEX	Controls the construction of the search index for both record search and dimension search.

Example

This example enables the Winery dimension for record search.

```
<RESEARCH_INDEX NAME="Winery" RESEARCH_HIERARCHY="TRUE">
  <SEARCH_INDEX>
    <POSITIONAL_INDEX/>
  </SEARCH_INDEX>
</RESEARCH_INDEX>
```

RESEARCH_INDEXES

A RESEARCH_INDEXES element lists the properties and dimensions enabled for record search.

Each property and dimension enabled for record search is specified in a RESEARCH_INDEX element.



Note: Several settings in this element are ignored starting with the MDEX Engine version 6.1.2. These settings are: MAX_NGRAM_LENGTH, DICTIONARY_MAX_NGRAM_LENGTH, and DICTIONARY_WILDCARD. Do not remove these settings from the file, since the DTD depends on them. Starting with the version 6.1.2, the MDEX Engine uses a simplified mechanism for wildcard search. This mechanism does not require specifying these settings. For more information on wildcard search, see the *Endeca MDEX Engine Basic Development Guide* version 6.1.2 or higher.

DTD

```
<!ELEMENT RESEARCH_INDEXES
  ( COMMENT?
    , RESEARCH_INDEX*
  )
>
<!ATTLIST RESEARCH_INDEXES
  INMEM_INDEX_THRESHOLD      CDATA      #IMPLIED
  MAX_NGRAM_LENGTH          CDATA      #IMPLIED
  DICTIONARY_WILDCARD       ( TRUE | FALSE ) #IMPLIED
  DICTIONARY_MAX_NGRAM_LENGTH CDATA      #IMPLIED
  MIN_WORD_OCCURRENCES      CDATA      #IMPLIED
  MIN_WORD_LENGTH           CDATA      #IMPLIED
  MAX_WORD_LENGTH           CDATA      #IMPLIED
>
```

Attributes

The following section describes the RESEARCH_INDEXES element's attributes.

INMEM_INDEX_THRESHOLD

In MDEX Engine 6.4.0, this attribute was deprecated. Specifies the maximum text size (in MB) for which text indexing will be done entirely in memory. If the text size is larger than this threshold, then temporary files on disk will be used. Typically, you do not need to modify the value of this attribute. However, there are two infrequent scenarios in which you may want to adjust the value of this attribute:

- If the machine running Dgidx has less than the recommended about of RAM, you might reduce this value.
- If other indexing structures cause Dgidx to run out of memory, you might reduce this value to allow more memory for other purposes.

MAX_NGRAM_LENGTH



Note: The value specified in this setting is ignored in the MDEX Engine starting with its version 6.1.2. However, do not remove this XML setting.

Specifies the maximum ngram length that should be indexed. All substrings of this length or shorter will be indexed. If a user does a wildcard search with a string that is less than or equal to this length, then exact results can be returned directly from the index. If the wildcard search includes a substring longer than this length, then the results returned from the index will be post-processed so that false positives are eliminated.

DICTIONARY_WILDCARD



Note: The value specified in this setting is ignored in the MDEX Engine starting with its version 6.1.2. However, do not remove this XML setting.

Specifies whether a wildcard index should be generated for the dictionary of words for the text collection containing this element. The default value of this attribute is TRUE when the containing element consists of off-line documents and FALSE otherwise.

DICTIONARY_MAX_NGRAM_LENGTH



Note: The value specified in this setting is ignored in the MDEX Engine starting with its version 6.1.2. However, do not remove this XML setting.

Specifies the maximum ngram length that should be indexed in the dictionary wildcard index.

MIN_WORD_OCCURRENCES

Specifies the minimum number of times a word must occur for it to be indexed for spelling correction. The default value is 4.

MIN_WORD_LENGTH

Specifies the minimum number of a characters that a word must contain for it to be indexed for spelling correction. The default value is 3 (words that are three characters or larger are added to the index).

MAX_WORD_LENGTH

Specifies the maximum number of a characters that a word may contain for it to be indexed for spelling correction. The default value is 16 (words that are 16 characters or fewer are added to the index).

Sub-elements

The following table provides a brief overview of the RECSEARCH_INDEXES sub-elements.

Sub-element	Brief description
COMMENT	Associates a comment with a parent element and preserves the comment when the file is rewritten. This element provides an alternative to using inline XML comments of the form <!-- ... -->.
RECSEARCH_INDEX	Enables a property or dimension for record search.

Example

This example enables a property (P_Description) and a dimension (Winery) for record search, including wildcard search.

```
<RECSERACH_INDEXES DICTIONARY_MAX_NGRAM_LENGTH="5"
  DICTIONARY_WILDCARD="TRUE" INMEM_INDEX_THRESHOLD="512"
  MAX_NGRAM_LENGTH="5" MAX_WORD_LENGTH="16"
  MIN_WORD_LENGTH="3" MIN_WORD_OCCURRENCES="4">
<RECSERACH_INDEX NAME="P_Description">
  <SEARCH_INDEX>
    <WILDCARD_INDEX/>
    <POSITIONAL_INDEX/>
  </SEARCH_INDEX>
</RECSERACH_INDEX>
<RECSERACH_INDEX NAME="Winery" RECSERACH_HIERARCHY="TRUE">
  <SEARCH_INDEX>
    <WILDCARD_INDEX/>
    <POSITIONAL_INDEX/>
  </SEARCH_INDEX>
</RECSERACH_INDEX>
```

Refinement_config.xml elements

The Refinement_config.xml file configures the ranking, sorting, clustering, and collapsing behaviors of refinement values returned from the MDEX Engine.

Each refinement is specified in a REFINEMENTS element and those are grouped in the root element REFINEMENTS_CONFIG.

CLUSTERS

A CLUSTERS element enables clustering for a given dimension and sets the parameters of each cluster.

For more details on clusters, see the *Endeca Relationship Discovery Guide*.

DTD

```
<!ELEMENT CLUSTERS EMPTY>
<!ATTLIST CLUSTERS
  NAME          CDATA      #REQUIRED
  COHERENCE     CDATA      #IMPLIED
  REC_SAMPLE_SIZE CDATA      #IMPLIED
  MAX_CLUSTERS  CDATA      #IMPLIED
  MAX_CLUSTER_SIZE CDATA      #IMPLIED
  MAX_CLUSTER_OVERLAP CDATA      #IMPLIED
  MAX_REFINEMENT_PRECISION CDATA      #IMPLIED
>
```

Attributes

The following sections describe the CLUSTERS element's attributes.

NAME

Specifies the name of the dimension for which to enable clustering. The dimension must be a related terms dimension.

COHERENCE

Specifies a number that governs the decision of whether a set of terms is coherent enough to form a cluster. The number must be between 0 and 10, where 10 leads to the smallest clusters and 0 leads to the largest. That is, low values are permissive (do not demand much coherence) and will result in fewer larger clusters, while high values are strict and will result in more smaller clusters. Defaults to 5.

REC_SAMPLE_SIZE

Specifies how many records from the current navigation state the MDEX Engine should consider when computing clusters. The range is from 50 to 2000, and the default is 500. Lower numbers will result in less memory consumption and faster turnaround from the MDEX Engine, but could produce less accurate results.

MAX_CLUSTERS

Specifies the maximum number of clusters that can be returned by the MDEX Engine. The range is from 2 to 10, with a default value of 6.

MAX_CLUSTER_SIZE

Specifies the maximum number of terms that can be in a cluster. The range is from 2 to 10, with a default value of 8.

MAX_CLUSTER_OVERLAP

Specifies the amount of overlap allowed between clusters. The range is from 0 to 10, with a default value of 5. If two clusters overlap (that is, if the document sets that each cluster maps to overlap), then the smaller cluster can be removed, depending on how big the overlap is. The value of this attribute dictates the overlap above which the smaller cluster is removed. If the value is set at 1, all smaller overlapping clusters are removed, even if they overlap by only one document; if the value is set at 10, only fully overlapping (subsumed) clusters are removed. A value of 0 will disable the overlapping cluster removal functionality.

MAX_REFINEMENT_PRECISION

Specifies the maximum precision for a refinement which is to be considered for clustering. The value is a floating number between 0 and 1, with a default of 0.4. Refinements with higher precision will be discarded. Setting this value lower prevents clustering refinements which essentially summarize a query.

Sub-elements

The CLUSTERS element has no sub-elements.

Example

This example enables clustering on the dimension named Related Terms.

```
<REFINEMENTS_CONFIG>
  <REFINEMENTS NAME="Related Terms" SORT_TYPE="ALPHA">
    <DYNAMIC_RANKING COUNT="10" MORE="FALSE"
      TOP_REFINEMENTS_SORT="DEFAULT" TYPE="FREQUENCY" />
  </REFINEMENTS>
  <CLUSTERS NAME="Related Terms" COHERENCE="4"
    MAX_CLUSTERS="5" REC_SAMPLE_SIZE="500" MAX_CLUSTER_SIZE="10"
    MAX_CLUSTER_OVERLAP="7" MAX_REFINEMENT_PRECISION="0.25" />
</REFINEMENTS_CONFIG>
```

DYNAMIC_RANKING

A DYNAMIC_RANKING element controls how refinements (dimension values) are returned from the dimension that contains this element.

If this element is included, then refinement ranking is enabled for this dimension.

DTD

```
<!ELEMENT DYNAMIC_RANKING EMPTY>
<!ATTLIST DYNAMIC_RANKING
  COUNT          CDATA          #IMPLIED
  MORE           (TRUE | FALSE)  #REQUIRED
  TYPE           (FREQUENCY | WEIGHTED_FREQUENCY) "FREQUENCY"
  TOP_REFINEMENTS_SORT (DYNAMIC_RANK | DEFAULT) "DYNAMIC_RANK"
>
```

Attributes

The following sections describe the DYNAMIC_RANKING element's attributes.

COUNT

Specifies the number of refinements (dimension values) that should be displayed for this dimension. If the number of refinements that are returned exceeds the value specified in COUNT, then a More link displays if MORE="TRUE".

MORE

When set to TRUE, the MDEX Engine computes the More refinement for dimensions and returns all of those dimension values. For example, if COUNT="100" and there are 1000 refinements returned, then clicking the More link displays the remaining 900.

When set to FALSE, the MDEX Engine computes the top refinements based on rank and returns those. The default value is TRUE.

TYPE

Specifies how the ranking for a particular refinement value is determined. There are two valid values:

- FREQUENCY determines the refinement ranking based on the number of records that the refinement value produces. The default value of TYPE is FREQUENCY.
- WEIGHTED_FREQUENCY determines a dimension value's rank by multiplying the number of records that it produces by the dimension value's static rank, which is assigned in dval_ranks.xml.



Note: In the MDEX 6.2.0 release, the WEIGHTED_FREQUENCY option has been deprecated.

TOP_REFINEMENTS_SORT

Specifies the order in which refinements are returned:

- DYNAMIC_RANK returns the refinements in refinement-rank order (refinements with higher rank are returned before refinements with lower rank).
- DEFAULT returns the refinements in the order specified by the SORT_ORDER attribute of the parent REFINEMENTS element.

The default value is DYNAMIC_RANK.

Sub-elements

The DYNAMIC_RANKING element has no sub-elements.

Example

This example sets dynamic ranking values for the Winery dimension.

```
<REFINEMENTS_CONFIG>
  <REFINEMENTS NAME="Winery" SORT_TYPE="ALPHA">
    <DYNAMIC_RANKING COUNT="20" MORE="FALSE"
      TOP_REFINEMENTS_SORT="DEFAULT" TYPE="FREQUENCY" />
  </REFINEMENTS>
</REFINEMENTS_CONFIG>
```

REFINEMENTS

The REFINEMENTS element specifies how dimensions behave when returned from the MDEX Engine as refinements.

DTD

```
<!ELEMENT REFINEMENTS
  ( STATS?
  , DYNAMIC_RANKING?
  )
>
<!ATTLIST REFINEMENTS
  NAME          CDATA          #REQUIRED
  SORT_TYPE     (ALPHA|NUMERIC) "ALPHA"
  SORT_ORDER    (ASC|DESC)      "ASC"
  DVAL_COLLAPSE_THRESHOLD CDATA          #IMPLIED
>
```

Attributes

The following sections describe the REFINEMENTS element's attributes.

NAME

Specifies a unique name for the refinement dimension.

SORT_TYPE

Specifies the order in which refinements from this dimension should be sorted when they are returned from the MDEX Engine:

- ALPHA sorts refinements alphabetically.
- NUMERIC sorts refinements numerically.

The default is ALPHA.

SORT_ORDER

Specifies the order in which refinements are returned:

- ASC specifies ascending order.
- DESC specifies descending order.

DVAL_COLLAPSE_THRESHOLD

Specifies the minimum number of refinements that must be children of a dimension value from this dimension before the refinements are collapsed into their parent.

A collapsible dimension value within this dimension will not be collapsed unless its number of refinements exceeds the DVAL_COLLAPSE_THRESHOLD value. For example, if a dimension named "Author" has a DVAL_COLLAPSE_THRESHOLD="20" and a dimension value within Author (such as "A") is marked COLLAPSIBLE="TRUE", then a search that returns 20 or more children is collapsed to display "A". The user can then expand "A" and its refinements. If the search returns 19 records or fewer, all the results are displayed (uncollapsed).

Sub-elements

The following table provides a brief overview of the REFINEMENTS sub-elements.

Sub-element	Brief description
STATS	Instructs the MDEX Engine to return statistics about refinements (dimension values) as part of the search query results.
DYNAMIC_RANKING	Controls how refinements (dimension values) are returned from the dimension that contains this element.

Example

This example shows the refinement settings for two dimensions.

```
<REFINEMENTS_CONFIG>
  <REFINEMENTS NAME="Winery" SORT_TYPE="ALPHA">
    <DYNAMIC_RANKING COUNT="20" MORE="FALSE"
      TOP_REFINEMENTS_SORT="DEFAULT" TYPE="FREQUENCY" />
  </REFINEMENTS>
  <REFINEMENTS DVAL_COLLAPSE_THRESHOLD="10"
    NAME="Price Range" SORT_TYPE="NUMERIC">
</REFINEMENTS_CONFIG>
```

REFINEMENTS_CONFIG

A REFINEMENTS_CONFIG element configures the ranking, sorting, clustering, and collapsing behaviors of refinement values returned from the MDEX Engine.

DTD

```
<!ELEMENT REFINEMENTS_CONFIG
  ( COMMENT?
    , (CLUSTERS | REFINEMENTS)*
    , STATS?
  )
>
```

Attributes

The REFINEMENTS_CONFIG element has no attributes.

Sub-elements

The following table provides a brief overview of the REFINEMENTS_CONFIG sub-elements.

Sub-element	Brief description
COMMENT	Associates a comment with a parent element and preserves the comment when the file is rewritten. This element provides an alternative to using inline XML comments of the form <!-- ... -->.
CLUSTERS	Enables and configures clustering for dimensions.
REFINEMENTS	Specifies how dimensions behave when returned from the MDEX Engine as refinements.
STATS	Instructs the MDEX Engine to return statistics about refinements (dimension values) as part of the search query results.

Example

This example shows the refinement settings for two dimensions.

```
<REFINEMENTS_CONFIG>
  <REFINEMENTS NAME="Winery" SORT_TYPE="ALPHA">
    <DYNAMIC_RANKING COUNT="20" MORE="FALSE"
      TOP_REFINEMENTS_SORT="DEFAULT" TYPE="FREQUENCY" />
  </REFINEMENTS>
  <REFINEMENTS DVAL_COLLAPSE_THRESHOLD="10"
    NAME="Price Range" SORT_TYPE="NUMERIC" >
</REFINEMENTS_CONFIG>
```

STATS

A STATS element instructs the MDEX Engine to return statistics about refinements (dimension values) as part of the search query results.

DTD

```
<!ELEMENT STATS EMPTY>
<!ATTLIST STATS
  NUM_RECORDS          ( TRUE  |  FALSE )  "FALSE"
  NUM_REFINEMENTS_IN_GROUP ( TRUE  |  FALSE )  "FALSE"
  MAX_RECORDS_COUNT    CDATA             "#IMPLIED"
  RECORD_COUNT_DISABLE_THRESHOLD CDATA             "#IMPLIED"
  DVAL_STATIC_RECORD_COUNT ( TRUE  |  FALSE )  "FALSE"
  DVAL_STATIC_RANK      ( TRUE  |  FALSE )  "#IMPLIED"
  REFINEMENT_RANK_SCORE ( TRUE  |  FALSE )  "#IMPLIED"
>
```

Attributes

The following sections describe the STATS element's attributes.

NUM_RECORDS

Specifies whether the MDEX Engine should compute the number of records associated with each refinement. This number is returned as a dimension value property in the MDEX Engine query results. The default value of this attribute is FALSE.

NUM_REFINEMENTS_IN_GROUP

Specifies whether the MDEX Engine should return the number of refinements in an expanded refinement group. This number is returned as a dimension value property in the MDEX Engine query results. The default value of this attribute is FALSE.

MAX_RECORDS_COUNT

Specifies the maximum number of records that should be returned for the record statistics on a refinement. This option is useful, if for example, you wish to know whether there are at least 1000 records for a particular refinement option, but you do not care if there are more than 1000. If you have enabled record statistics in the MDEX Engine indexer configuration file, reducing this number will improve the performance of the MDEX Engine. Note that this threshold applies to all dimensions. By default, there is no threshold for the record statistics computation.

RECORD_COUNT_DISABLE_THRESHOLD

Specifies the maximum number of records in a result set above which record statistics should not be computed for the refinements. By default, there is no threshold for disabling the record statistics computation.

DVAL_STATIC_RECORD_COUNT

Specifies whether the number of records associated with each dimension value should be returned as a dimension value property when that dimension value is returned by the MDEX Engine (for example, as a refinement). The number of records associated with each dimension value in this case is statically determined during indexing, and is the total number of records in the data set that have the dimension value. The default value is FALSE.

DVAL_STATIC_RANK

Specifies whether every dimension value's static rank should be returned as a property on the dimension value. The default value is FALSE.



Note: This attribute is reinstated starting with the MDEX Engine release 6.1.4. This attribute has been deprecated in 6.0.0-6.1.3 releases of MDEX Engine. If this attribute was used in releases of the MDEX Engine 6.0.0 through 6.1.3, the MDEX Engine ignored it and issued a warning about its presence in the file.

REFINEMENT_RANK_SCORE

Specifies whether the MDEX Engine should return the rank of each refinement that is from a ranked dimension. If set to TRUE, then each refinement's rank is returned as a dimension value property. This attribute affects pre-computation and the run-time operation of the MDEX Engine. The default value is FALSE.

Sub-elements

STATS contains no sub-elements.

Example

This example shows a simple usage of STATS.

```
<STATS NUM_RECORDS="TRUE" MAX_RECORDS_COUNT="500" />
```

Relrank_strategies.xml elements

The Relrank_strategies.xml file contains the relevance ranking strategies for an application.

The strategies are grouped in the root element RELRANK_STRATEGIES. Each strategy is expressed in a RELRANK_STRATEGY element, which in turn is made of individual relevance ranking modules such as RELRANK_EXACT, RELRANK_FIELD, and so on.

For more information about relevance ranking, see "Using Relevance Ranking" in the *Endeca MDEX Engine Advanced Development Guide*.

RELRANK_APPROXPHRASE

The RELRANK_APPROXPHRASE element implements the Approximate Phrase relevance ranking module.

This module is similar to RELRANK_PHRASE, except that in the higher stratum, only the first instance of an exact match of the user's phrase is considered, which improves system performance.



Note: The RELRANK_APPROXPHRASE element is no longer supported. Use the RELRANK_PHRASE element with the APPROXIMATE attribute instead.

DTD

```
<!ELEMENT RELRANK_APPROXPHRASE EMPTY>
```

Attributes

The RELRANK_APPROXPHRASE element has no attributes.

Sub-elements

The RELRANK_APPROXPHRASE element has no sub-elements.

RELRANK_EXACT

The RELRANK_EXACT element implements the Exact relevance ranking module.

This module groups results into strata based on how well they match a query string, with the highest stratum containing results that match the user's query exactly. See "Using Relevance Ranking" in the *Endeca Advanced Development Guide* for details.

DTD

```
<!ELEMENT RELRANK_EXACT EMPTY>
```

Attributes

The RELRANK_EXACT element has no attributes.

Sub-elements

The RELRANK_EXACT element has no sub-elements.

Example

In this example, the ranking strategy MyStrategy includes the RELRANK_EXACT element.

```
<RELRANK_STRATEGY NAME="MyStrategy">
  <RELRANK_STATIC NAME="Availability" ORDER="DESCENDING" />
  <RELRANK_EXACT />
  <RELRANK_STATIC NAME="Price" ORDER="ASCENDING" />
</RELRANK_STRATEGY>
```

RELRANK_FIELD

The RELRANK_FIELD element implements the Field relevance ranking module.

This module assigns a score to each result based on the static rank of the dimension or property member of the search interface that caused the document to match the query. See "Using Relevance Ranking" in the *Endeca Advanced Development Guide* for details.

DTD

```
<!ELEMENT RELRANK_FIELD EMPTY>
```

Attributes

The RELRANK_FIELD element has no attributes.

Sub-elements

The RELRANK_FIELD element has no sub-elements.

Example

In this example, the field module is included in a strategy called All_Fields.

```
<RELRANK_STRATEGY NAME="All_Fields">
  <RELRANK_EXACT />
  <RELRANK_INTERP />
  <RELRANK_FIELD />
</RELRANK_STRATEGY>
```

RELRANK_FIRST

The RELRANK_FIRST element implements the First relevance ranking module.

This module ranks documents by how close the query terms are to the beginning of the document. This module takes advantage of the fact that the closer something is to the beginning of a document, the more likely it is to be relevant. See "Using Relevance Ranking" in the *Endeca MDEX Engine Advanced Development Guide* for details.

DTD

```
<!ELEMENT RELRANK_FIRST EMPTY>
```

Attributes

The RELRANK_FIRST element has no attributes.

Sub-elements

The RELRANK_FIRST element has no sub-elements.

Example

In this example, the ranking strategy All includes the First relevance ranking module.

```
<RELRANK_STRATEGY NAME="All">
  <RELRANK_FIRST/>
  <RELRANK_INTERP/>
  <RELRANK_FIELD/>
</RELRANK_STRATEGY>
```

RELRANK_FREQ

The RELRANK_FREQ element implements the Frequency relevance ranking module.

This module provides result scoring based on the frequency (number of occurrences) of the user's query terms in the result text. See "Using Relevance Ranking" in the *Endeca MDEX Engine Advanced Development Guide* for details.

DTD

```
<!ELEMENT RELRANK_FREQ EMPTY>
```

Attributes

The RELRANK_FREQ element has no attributes.

Sub-elements

The RELRANK_FREQ element has no sub-elements.

Example

This example implements a strategy called Frequency.

```
<RELRANK_STRATEGY NAME="Frequency">
  <RELRANK_FREQ/>
</RELRANK_STRATEGY>
```

RELRANK_GLOM

The RELRANK_GLOM element implements the Glom relevance ranking module.

This module ranks single-field matches ahead of cross-field matches. See "Using Relevance Ranking" in the *Endeca MDEX Engine Advanced Development Guide* for details.

DTD

```
<!ELEMENT RELRANK_GLOM EMPTY>
```

Attributes

The RELRANK_GLOM element has no attributes.

Sub-elements

The RELRANK_GLOM element has no sub-elements.

Example

This example implements a strategy called Single_Field.

```
<RELRANK_STRATEGY NAME="Single_Field">
  <RELRANK_GLOM/>
</RELRANK_STRATEGY>
```

RELRANK_INTERP

The RELRANK_INTERP element implements the Interpreted (Interp) relevance ranking module.

This module provides a general-purpose strategy that assigns a score to each result document based on the query processing techniques used to obtain the match. Matching techniques considered include partial matching, cross-attribute matching, spelling correction, thesaurus, and stemming matching. See "Using Relevance Ranking" in the *Endeca MDEX Engine Advanced Development Guide* for details.

DTD

```
<!ELEMENT RELRANK_INTERP EMPTY>
```

Attributes

The RELRANK_INTERP element has no attributes.

Sub-elements

The RELRANK_INTERP element has no sub-elements.

Example

In this example, the Interpreted module is included in a strategy called All_Fields.

```
<RELRANK_STRATEGY NAME="All_Fields">
  <RELRANK_EXACT/>
  <RELRANK_INTERP/>
  <RELRANK_FIELD/>
</RELRANK_STRATEGY>
```

RELRANK_MAXFIELD

The RELRANK_MAXFIELD element implements the Maximum Field (Maxfield) relevance ranking module.

This module is similar to the Field strategy module, except it selects the static field-specific score of the highest-ranked field that contributed to the match. See "Using Relevance Ranking" in the *Endeca MDEX Engine Advanced Development Guide* for details.

DTD

```
<!ELEMENT RELRANK_MAXFIELD EMPTY>
```

Attributes

The RELRANK_MAXFIELD element has no attributes.

Sub-elements

The RELRANK_MAXFIELD element has no sub-elements.

Example

This example implements a strategy called High_Rank.

```
<RELRANK_STRATEGY NAME="High_Rank">
  <RELRANK_MAXFIELD/>
</RELRANK_STRATEGY>
```

RELRANK_MODULE

The RELRANK_MODULE element is used to refer to and compose other relevance ranking modules into strategies.

DTD

```
<!ELEMENT RELRANK_MODULE (RELRANK_MODULE_PARAM*)>
<!ATTLIST RELRANK_MODULE
  NAME      CDATA      #REQUIRED
>
```

Attributes

The following section describes the RELRANK_MODULE attribute.

NAME

NAME refers to another defined relevance ranking module.

Sub-elements

The RELRANK_MODULE element has no supported sub-elements. RELRANK_MODULE_PARAM is not supported.

Example

In this example, a strategy called Best Price is defined. Later, this strategy is included in another strategy definition using the RELRANK_MODULE element.

```
<RELRANK_STRATEGY NAME="Best Price">
  <RELRANK_STATIC NAME="Price" ORDER="ASCENDING" />
</RELRANK_STRATEGY>
<RELRANK_STRATEGY NAME="MyStrategy">
  <RELRANK_STATIC NAME="Availability" ORDER="DESCENDING" />
  <RELRANK_EXACT/>
  <RELRANK_MODULE NAME="Best Price"/>
</RELRANK_STRATEGY>
```

RELRANK_NTERMS

The RELRANK_NTERMS element implements the Number of Terms (Nterms) relevance ranking module.

This module assigns a score to each result record based on the number of query terms that the result record matches. For example, in a three-word query, results that match all three words are ranked above results that match only two words, which are ranked above results that match only one word. See "Using Relevance Ranking" in the *Endeca MDEX Engine Advanced Development Guide* for details.

This module applies only to search modes where the number of results can vary in how many query terms they match. These search modes include matchpartial, matchany, matchallpartial, and matchallany. See "Using Search Modes" in the *Endeca MDEX Engine Basic Developer's Guide* for details.

DTD

```
<!ELEMENT RELRANK_NTERMS EMPTY>
```

Attributes

The RELRANK_NTERMS element has no attributes.

Sub-elements

The RELRANK_NTERMS element has no sub-elements.

Example

In this example, the Nterms module is included in a strategy called NumberOfTerms.

```
<RELRANK_STRATEGY NAME="NumberOfTerms">
  <RELRANK_NTERMS/>
</RELRANK_STRATEGY>
```

RELRANK_NUMFIELDS

The RELRANK_NUMFIELDS element implements the Number of Fields (Numfields) relevance ranking module.

This module ranks results based on the number of fields in the associated search interface in which a match occurs. See "Using Relevance Ranking" in the *Endeca MDEX Engine Advanced Development Guide* for details.

DTD

```
<!ELEMENT RELRANK_NUMFIELDS EMPTY>
```

Attributes

The RELRANK_NUMFIELDS element has no attributes.

Sub-elements

The RELRANK_NUMFIELDS element has no sub-elements.

Example

This example implements the Numfields relevance ranking module.

```
<RELRANK_STRATEGY NAME="NumFields">
  <RELRANK_NUMFIELDS/>
</RELRANK_STRATEGY>
```

RELRANK_PHRASE

The RELRANK_PHRASE element implements the Phrase relevance ranking module.

This module states that results containing the user's query as an exact phrase, or a subset of the exact phrase, should be considered more relevant than matches simply containing the user's search terms scattered throughout the text. Note that records that have the phrase are ranked higher than records which do not contain the phrase. See "Using Relevance Ranking" in the *Endeca MDEX Engine Advanced Development Guide* for details.

DTD

```
<!ELEMENT RELRANK_PHRASE EMPTY>
<!ATTLIST RELRANK_PHRASE
  SUBPHRASE      ( TRUE | FALSE )    " FALSE "
  APPROXIMATE    ( TRUE | FALSE )    " FALSE "
  QUERY_EXPANSION ( TRUE | FALSE )  " FALSE "
>
```

Attributes

The following sections describe the RELRANK_PHRASE element's attributes.

SUBPHRASE

If set to TRUE, enables subphrasing, which ranks results based on the length of their subphrase matches.

If set to FALSE (the default), subphrasing is not enabled, which means that results are ranked into two strata: those that matched the entire phrase and those that did not.

APPROXIMATE

If set to TRUE, approximate matching is enabled. In this case, the Phrase module looks at a limited number of positions in each result that a phrase match could possibly exist, rather than all the positions. Only this limited number of possible occurrences is considered, regardless of whether there are later occurrences that are better, more relevant matches.

QUERY_EXPANSION

If set to TRUE, enables query expansion, in which spelling correction, thesaurus, and stemming adjustments are applied to the original phrase. With query expansion enabled, the Phrase module ranks results that match a phrase's expanded forms in the same stratum as results that match the original phrase.

Sub-elements

The RELRANK_PHRASE element has no sub-elements.

Example

This example of the Phrase module enables approximate matching and query expansion, and disables subphrasing.

```
<RELRANK_STRATEGY NAME="PhraseMatch">
  <RELRANK_PHRASE APPROXIMATE="TRUE"
    QUERY_EXPANSION="TRUE" SUBPHRASE="FALSE" />
</RELRANK_STRATEGY>
```

RELRANK_PROXIMITY

The RELRANK_PROXIMITY element implements the Proximity relevance ranking module.

This module ranks how close the query terms are to each other in a document by counting the number of intervening words. See "Using Relevance Ranking" in the *Endeca MDEX Engine Advanced Development Guide* for details.

DTD

```
<!ELEMENT RELRANK_PROXIMITY EMPTY>
```

Attributes

The RELRANK_PROXIMITY element has no attributes.

Sub-elements

The RELRANK_PROXIMITY element has no sub-elements.

Example

This example implements a strategy called All that includes the Proximity module.

```
<RELRANK_STRATEGY NAME="All">
  <RELRANK_PROXIMITY/>
  <RELRANK_INTERP/>
  <RELRANK_FIELD/>
</RELRANK_STRATEGY>
```

RELRANK_SPELL

The RELRANK_SPELL element implements the Spell relevance ranking module.

This module ranks matches that do not require spelling correction ahead of spelling-corrected matches. See "Using Relevance Ranking" in the *Endeca MDEX Engine Advanced Development Guide* for details.

DTD

```
<!ELEMENT RELRANK_SPELL EMPTY>
```

Attributes

The RELRANK_SPELL element has no attributes.

Sub-elements

The RELRANK_SPELL element has no sub-elements.

Example

This example implements a strategy called TrueMatch.

```
<RELRANK_STRATEGY NAME="TrueMatch">
  <RELRANK_SPELL/>
</RELRANK_STRATEGY>
```

RELRANK_STATIC

The RELRANK_STATIC element implements the Static relevance ranking module.

This module assigns a constant score to each result, depending on the type of search operation performed. See "Using Relevance Ranking" in the *Endeca MDEX Engine Advanced Development Guide* for details.

DTD

```
<!ELEMENT RELRANK_FREQ EMPTY>
<!ATTLIST RELRANK_STATIC
  NAME      CDATA          #REQUIRED
  ORDER     (ASCENDING|DESCENDING) #REQUIRED
>
```

Attributes

The following sections describe the RELRANK_STATIC attributes.

NAME

Specifies the name of a property or dimension that used for static relevance ranking.

ORDER

Specifies how records should be sorted with respect to the specified property or dimension.

Sub-elements

The RELRANK_STATIC element has no sub-elements.

Example

In this example, the BestPrice strategy consists of the Price dimension sorted from lowest to highest.

```
<RELRANK_STRATEGY NAME="BestPrice">
  <RELRANK_STATIC NAME="Price" ORDER="ASCENDING" />
</RELRANK_STRATEGY>
```

RELRANK_STRATEGIES

A RELRANK_STRATEGIES element contains any number of relevance ranking strategies for an application.

Each strategy is specified in a RELRANK_STRATEGY element.

DTD

```
<!ELEMENT RELRANK_STRATEGIES
  ( COMMENT?
    , RELRANK_STRATEGY*
  )
>
```

Attributes

The RELRANK_STRATEGIES element has no attributes.

Sub-elements

The following table provides a brief overview of the RELRANK_STRATEGIES sub-elements.

Sub-element	Brief description
COMMENT	Associates a comment with a parent element and preserves the comment when the file is rewritten. This element provides an alternative to using inline XML comments of the form <!-- ... -->.
RELRANK_STRATEGY	Contains a list of relevance ranking strategies that affect the order in which search results are returned to a user.

Example

This example shows several strategies grouped under the root element RELRANK_STRATEGIES.

```
<RELRANK_STRATEGIES>
  <RELRANK_STRATEGY NAME="Bestseller Strategy">
    <RELRANK_STATIC NAME="Bestseller" ORDER="DESCENDING"/>
  </RELRANK_STRATEGY>
  <RELRANK_STRATEGY NAME="Electronics Strategy">
    <RELRANK_FIELD/>
    <RELRANK_EXACT/>
    <RELRANK_INTERP/>
    <RELRANK_STATIC NAME="Bestseller" ORDER="DESCENDING"/>
    <RELRANK_STATIC NAME="Product_Name" ORDER="ASCENDING"/>
  </RELRANK_STRATEGY>
</RELRANK_STRATEGIES>
```

RELRANK_STRATEGY

The RELRANK_STRATEGY element contains a list of relevance ranking strategies that affect the order in which search results are returned to a user.

Each sub-element of RELRANK_STRATEGY represents a specific type of strategy. If you want several relevance ranking strategies to affect search result, then the order of the sub-elements, which represent the strategies, is significant. The order of the sub-elements defines the order in which the strategies are applied to the search results. See "Using Relevance Ranking" in the *Endeca MDEX Engine Advanced Development Guide* for details.

DTD

```
<!ELEMENT RELRANK_STRATEGY (
  RELRANK_STATIC
  | RELRANK_EXACT
  | RELRANK_PHRASE
)>
```

```

RELRANK_APPROXPHRASE
RELRANK_GLOM
RELRANK_SPELL
RELRANK_FIELD
RELRANK_MAXFIELD
RELRANK_INTERP
RELRANK_FREQ
RELRANK_WFREQ
RELRANK_NTERMS
RELRANK_PROXIMITY
RELRANK_FIRST
RELRANK_NUMFIELDS
RELRANK_MODULE
) +>
<!ATTLIST RELRANK_STRATEGY
  NAME      CDATA      #REQUIRED
>

```

Attributes

The following section describes the RELRANK_STRATEGY attribute.

NAME

Specifies the name of the strategy.

Sub-elements

The following table provides a brief overview of the RELRANK_STRATEGY sub-elements.

Sub-element	Brief description
RELRANK_STATIC	Assigns a constant score to each result, depending on the type of search operation perform.
RELRANK_EXACT	Groups results into strata based on how well they match the query string, with the highest stratum containing results that match the user's query exactly.
RELRANK_PHRASE	Considers results containing the user's query as an exact phrase, or a subset of the exact phrase, to be more relevant than matches simply containing the user's search terms scattered throughout the text.
RELRANK_APPROXPHRASE	Not supported.
RELRANK_GLOM	Ranks single-field matches ahead of cross-field matches.
RELRANK_SPELL	Ranks true matches ahead of spelling-corrected matches.
RELRANK_FIELD	Assigns a score to each result based on the static rank of the dimension or property member of the search interface that caused the document to match the query.
RELRANK_MAXFIELD	Similar to the Field strategy, except it selects the static field-specific score of the highest-ranked field that contributed to the match.
RELRANK_INTERP	A general-purpose strategy that assigns a score to each result document based on the query processing techniques used to obtain the match. Matching techniques considered include partial matching,

Sub-element	Brief description
	cross-attribute matching, spelling correction, thesaurus, and stemming matching.
RELRANK_FREQ	Provides result scoring based on the frequency (number of occurrences) of the user's query terms in the result text.
RELRANK_WFREQ	Scores results based on the frequency of user query terms in the result, while weighing the individual query term frequencies for each result by the information content (overall frequency in the complete data set) of each query term.
RELRANK_NTERMS	Assigns a score to each result record based on the number of query terms that the result record matches.
RELRANK_PROXIMITY	Ranks how close the query terms are to each other in a document by counting the number of intervening words.
RELRANK_FIRST	Ranks documents by how close the query terms are to the beginning of the document.
RELRANK_NUMFIELDS	Ranks results based on the number of fields in the associated search interface in which a match occurs.
RELRANK_MODULE	Used to refer to other RELRANK elements and compose them into cohesive strategies.

Example

This example presents a ranking strategy called Product_Search_Rank, which itself is composed of multiple strategies.

```
<RELRANK_STRATEGY NAME="Product_Search_Rank">
  <RELRANK_MODULE NAME="IsAvailable"/>
  <RELRANK_FIELD/>
  <RELRANK_PHRASE/>
  <RELRANK_MODULE NAME="BestPrice"/>
</RELRANK_STRATEGY>
```

RELRANK_WFREQ

The RELRANK_WFREQ element implements the Weighted Frequency (Wfreq) relevance ranking module.

This module scores results based on the frequency of user query terms in the result, while weighing the individual query term frequencies for each result by the information content (overall frequency in the complete data set) of each query term. See "Using Relevance Ranking" in the *Endeca MDEX Engine Advanced Development Guide* for details.

DTD

```
<!ELEMENT RELRANK_WFREQ EMPTY>
```

Attributes

The RELRANK_WFREQ element has no attributes.

Sub-elements

The RELRANK_WFREQ element has no sub-elements.

Example

This example implements a strategy called Term_Freq.

```
<RELRANK_STRATEGY NAME="Term_Freq">
  <RELRANK_WFREQ/>
</RELRANK_STRATEGY>
```

Render_config.xml elements

The Render_config.xml file specifies the properties and dimensions that may be rendered on a record page or a record list page.

Each property or dimension is specified in a RENDER element. RENDER elements are grouped in the RENDER_CONFIG parent element.

RENDER

A RENDER element controls whether specified properties or dimensions may be rendered on a record list page or a record page.

DTD

```
<!ELEMENT RENDER EMPTY>
<!ATTLIST RENDER
  NAME          CDATA          #REQUIRED
  RENDER_PROD_LIST  ( FALSE | TRUE )  " TRUE "
  RENDER_PROD_PAGE  ( FALSE | TRUE )  " TRUE "
>
```

Attributes

The following sections describe the RENDER element's attributes.

NAME

Specifies the name of the property or dimension.

RENDER_PROD_LIST

Specifies whether the MDEX Engine returns this property or dimension along with a record on the record list page. The default value is TRUE.

RENDER_PROD_PAGE

Specifies whether the MDEX Engine returns this property or dimension along with a record on the product page. The default value is TRUE.

Sub-elements

The RENDER element has no sub-elements.

Example

This example shows rendering configuration for a small number of properties.

```
<RENDER_CONFIG>
  <RENDER NAME="Camcorder_Features_Attr"
    RENDER_PROD_PAGE="TRUE" RENDER_PROD_LIST="TRUE" />
  <RENDER NAME="Camcorder_Formats_Attr"
    RENDER_PROD_PAGE="TRUE" RENDER_PROD_LIST="TRUE" />
  <RENDER NAME="Camcorder_Size_Attr"
    RENDER_PROD_PAGE="TRUE" RENDER_PROD_LIST="TRUE" />
  <RENDER NAME="Camera_Types_Attr"
    RENDER_PROD_PAGE="TRUE" RENDER_PROD_LIST="TRUE" />
</RENDER_CONFIG>
```

RENDER_CONFIG

A RENDER_CONFIG element specifies the properties and dimensions that may be rendered on a product page or a record list page.

Each property or dimension is specified in a RENDER element.

DTD

```
<!ELEMENT RENDER_CONFIG
  ( COMMENT?
    , RENDER*
  )
>
```

Attributes

The RENDER_CONFIG element has no attributes.

Sub-elements

The following table provides a brief overview of the RENDER_CONFIG sub-elements.

Sub-element	Brief description
COMMENT	Associates a comment with a parent element and preserves the comment when the file is rewritten. This element provides an alternative to using inline XML comments of the form <!-- ... -->.
RENDER	Controls whether specified properties or dimensions may be rendered on a record list page or a product page.

Example

This example shows rendering configuration for a small number of properties.

```
<RENDER_CONFIG>
  <RENDER NAME="Camcorder_Features_Attr"
    RENDER_PROD_PAGE="TRUE" RENDER_PROD_LIST="TRUE" />
  <RENDER NAME="Camcorder_Formats_Attr"
    RENDER_PROD_PAGE="TRUE" RENDER_PROD_LIST="TRUE" />
  <RENDER NAME="Camcorder_Size_Attr"
    RENDER_PROD_PAGE="TRUE" RENDER_PROD_LIST="TRUE" />
  <RENDER NAME="Camera_Types_Attr"
    RENDER_PROD_PAGE="TRUE" RENDER_PROD_LIST="TRUE" />
</RENDER_CONFIG>
```

```
    RENDER_PROD_PAGE="TRUE"  RENDER_PROD_LIST="TRUE" />
</RENDER_CONFIG>
```

Rollups.xml elements

The Rollups.xml file enables record aggregation based on a property or dimension value key.

By rolling up records based on a key, the MDEX Engine can handle multiple records as a single record. The ROLLUP element indicates a rollup key for record aggregation. ROLLUP elements are grouped in the ROLLUPS parent element. For more information, see "Creating Aggregated Records" in the *Endeca MDEX Engine Basic Development Guide*.

ROLLUP

A ROLLUP element specifies a rollup key for record aggregation.

A rollup key may be either a dimension name or property name.

DTD

```
<!ELEMENT ROLLUP EMPTY>
<!ATTLIST ROLLUP
  NAME      CDATA      #REQUIRED
>
```

Attributes

The following section describes the ROLLUP element's attribute.

NAME

Specifies a dimension name or property name that is used as a rollup key.

Sub-elements

The ROLLUP element has no sub-elements.

Example

This example shows two rollup keys.

```
<ROLLUPS>
  <ROLLUP NAME="Manufacturer" />
  <ROLLUP NAME="Companies" />
</ROLLUPS>
```

ROLLUPS

A ROLLUPS element contains any number of rollup keys indicated by ROLLUP elements.

DTD

```
<!ELEMENT ROLLUPS
  ( COMMENT?
  , ROLLUP* )>
```

```
    )  
>
```

Attributes

The ROLLUPS element has no attributes.

Sub-elements

The following table provides a brief overview of the ROLLUPS sub-elements.

Sub-element	Brief description
COMMENT	Associates a comment with a parent element and preserves the comment when the file is rewritten. This element provides an alternative to using inline XML comments of the form <!-- ... -->.
ROLLUP	Specifies a rollup key for record aggregation.

Example

This example shows two rollup keys.

```
<ROLLUPS>  
  <ROLLUP NAME="Manufacturer" />  
  <ROLLUP NAME="Companies" />  
</ROLLUPS>
```

Search_chars.xml elements

The Search_chars.xml file contains searchable characters for your application.

The MDEX Engine treats such characters as searchable rather than treating them as punctuation. For more detailed information, see "Using Search Characters" in the *Endeca MDEX Engine Basic Development Guide*.

SEARCH_CHAR

The SEARCH_CHAR element specifies a character that should be treated as a searchable character, instead of as punctuation.

DTD

```
<!ELEMENT SEARCH_CHAR (#PCDATA)>
```

Attributes

The SEARCH_CHAR element has no attributes.

Sub-elements

The SEARCH_CHAR element has no sub-elements.

Example

In this example, to allow searching on "C++" and on "C#", you would specify:

```
<SEARCH_CHARS>
  <SEARCH_CHAR>+</SEARCH_CHAR>
  <SEARCH_CHAR>#</SEARCH_CHAR>
</SEARCH_CHARS>
```

SEARCH_CHARS

A SEARCH_CHARS element specifies the search characters enabled in your application.

Each search character is represented by a SEARCH_CHAR element.

DTD

```
<!ELEMENT SEARCH_CHARS
  ( COMMENT?
    , SEARCH_CHAR*
  )
>
```

Attributes

The SEARCH_CHARS element has no attributes.

Sub-elements

The following table provides a brief overview of the SEARCH_CHARS sub-elements.

Sub-element	Brief description
COMMENT	Associates a comment with a parent element and preserves the comment when the file is rewritten. This element provides an alternative to using inline XML comments of the form <!-- ... -->.
SEARCH_CHAR	Specifies a character that should be treated as a searchable character, instead of as punctuation.

Example

In this example, to allow searching on "C++" and on "C#", you would specify:

```
<SEARCH_CHARS>
  <SEARCH_CHAR>+</SEARCH_CHAR>
  <SEARCH_CHAR>#</SEARCH_CHAR>
</SEARCH_CHARS>
```

Searchindex.xml elements

The Searchindex.xml file contains elements used to build indexes that serve to boost performance in searching.

The root element is SEARCH_INDEX. Its sub-elements optimize indexes for particular types of searches and consequently, SEARCH_INDEX may be found in other .xml files. For example, SEARCH_INDEX may be found in dimsearch_index.xml and recsearch_indexes.xml.

POSITIONAL_INDEX

The POSITIONAL_INDEX element specifies that a word position index should be created for the text collection containing this element.

Word position indices speed up the performance of phrase queries on large or off-line data sources such as property values with long descriptions or large amounts of document text.

DTD

```
<!ELEMENT POSITIONAL_INDEX EMPTY>
```

Attributes

The POSITIONAL_INDEX element has no attributes.

Sub-elements

The POSITIONAL_INDEX element has no sub-elements.

Example

This example enables positional indexing and wildcard indexing for searching on the Description property.

```
<RECSERACH_INDEX NAME="Description">
  <SEARCH_INDEX>
    <WILDCARD_INDEX />
    <POSITIONAL_INDEX />
  </SEARCH_INDEX>
</RECSERACH_INDEX>
```

SEARCH_INDEX

The SEARCH_INDEX element specifies whether the wildcard index should be created for both record search and dimension search.

DTD

```
<!ELEMENT SEARCH_INDEX
  ( WILDCARD_INDEX?
    , POSITIONAL_INDEX?
    , WORDAFFINITY_INDEX?
  )
>
<!ATTLIST SEARCH_INDEX
  INDEX_BUCKET_SIZE      CDATA      #IMPLIED
  INMEM_INDEX_THRESHOLD  CDATA      #IMPLIED
  TEXTSEARCH_SIZE_EST    CDATA      #IMPLIED
  MIN_WORD_OCCURRENCES  CDATA      #IMPLIED
  MIN_WORD_LENGTH        CDATA      #IMPLIED
  MAX_WORD_LENGTH        CDATA      #IMPLIED
>
```

Attributes

The following sections describe the SEARCH_INDEX element's attributes.

INDEX_BUCKET_SIZE

This attribute is deprecated.

INMEM_INDEX_THRESHOLD

This attribute has been moved to RESEARCH_INDEXES and DIMSEARCH_INDEX.

TEXTSEARCH_SIZE_EST

This attribute is deprecated.

MIN_WORD_OCCURRENCES

This attribute has been moved to RESEARCH_INDEXES and DIMSEARCH_INDEX.

MIN_WORD_LENGTH

This attribute has been moved to RESEARCH_INDEXES and DIMSEARCH_INDEX.

MAX_WORD_LENGTH

This attribute has been moved to RESEARCH_INDEXES and DIMSEARCH_INDEX.

Sub-elements

The following table provides a brief overview of the SEARCH_INDEX sub-elements. Note that the WORDAFFINITY_INDEX element is deprecated.

Sub-element	Brief description
WILDCARD_INDEX	Specifies that a wildcard index should be created for the text collection that contains this element.
POSITIONAL_INDEX	Specifies that a word position index should be created for the text collection that contains this element.

Example

This example enables positional indexing and wildcard indexing for searching on the Description property.

```
<RESEARCH_INDEX NAME="Description">
  <SEARCH_INDEX>
    <WILDCARD_INDEX/>
    <POSITIONAL_INDEX/>
  </SEARCH_INDEX>
</RESEARCH_INDEX>
```

WILDCARD_INDEX

The WILDCARD_INDEX element specifies that a wildcard index should be created for the text collection that contains it.

In addition, this element allows you to control the behavior of the construction of the wildcard index itself. Wildcard indices enable wildcard search, which is the ability to match user query terms to fragments of words in indexed text. The fragments themselves are referred to as *ngrams*.

DTD

```
<!ELEMENT WILDCARD_INDEX EMPTY>
<!ATTLIST WILDCARD_INDEX
  MAX_NGRAM_LENGTH          CDATA      #IMPLIED
  DICTIONARY_WILDCARD        (TRUE|FALSE) #IMPLIED
  DICTIONARY_MAX_NGRAM_LENGTH CDATA      #IMPLIED
>
```

Attributes

The following sections describe the WILDCARD_INDEX element's attributes.

MAX_NGRAM_LENGTH

Specifies the maximum ngram length that should be indexed. All substrings of this length or shorter will be indexed. If a user does a wildcard search with a string that is less than or equal to this length, then exact results can be returned directly from the index. If the wildcard search includes a substring longer than this length, then the results returned from the index will be post-processed so that false positives are eliminated.

DICTIONARY_WILDCARD

Specifies whether a wildcard index should be generated for the dictionary of words for the text collection containing this element. The default value of this attribute is TRUE when the containing element consists of off-line documents and FALSE otherwise.

DICTIONARY_MAX_NGRAM_LENGTH

Specifies the maximum ngram length that should be indexed in the dictionary wildcard index.

Sub-elements

The WILDCARD_INDEX element has no sub-elements.

Example

This example enables positional indexing and wildcard indexing for searching on the Description property.

```
<RECREARCH_INDEX NAME="Description">
  <SEARCH_INDEX>
    <WILDCARD_INDEX/>
    <POSITIONAL_INDEX/>
  </SEARCH_INDEX>
</RECREARCH_INDEX>
```

Search_interface.xml elements

The Search_interface.xml contains elements used to build and configure search interfaces.

The file's root element is SEARCH_INTERFACE. Search interfaces control record search behavior for groups of one or more properties or dimensions. For more information, see "About Search Interfaces" in the *Endeca Basic Development Guide*.

AUTO_SUGGEST

The AUTO_SUGGEST element specifies how to configure automatic spelling correction for either record searches or dimension searches.

If you want to use automatic spelling correction in record searches, you must first enable it by setting ENABLE_AUTO_SUGGEST to TRUE in the RECSEARCH_CONFIG element. If you want to use automatic spelling correction in dimension searches, you must first enable it by setting ENABLE_AUTO_SUGGEST to TRUE in the DIMSEARCH_CONFIG element.

For more information about spelling corrections, see "Using Spelling Correction and Did You Mean" in the *Endeca MDEX Engine Advanced Development Guide*.

DTD

```
<!ELEMENT AUTO_SUGGEST (SEARCH_CORRECTION_PARAMETERS)>
```

Attributes

The AUTO_SUGGEST element has no attributes.

Sub-elements

The following table provides a brief overview of the AUTO_SUGGEST sub-element.

Sub-element	Brief description
SEARCH_CORRECTION_PARAMETERS	Specifies general spelling correction parameters for Did You Mean and automatic spelling correction.

DID_YOU_MEAN

The DID_YOU_MEAN element specifies how to configure explicit alternatives for search terms as a part of spelling correction.

If you want to use Did You Mean alternative terms as a part of spelling correction, you must first enable Did You Mean by setting ENABLE_DID_YOU_MEAN to TRUE in the RECSEARCH_CONFIG element. For more information about spelling corrections, see "Using Spelling Correction and Did You Mean" in the *Endeca Advanced Development Guide*.

DTD

```
<!ELEMENT DID_YOU_MEAN (SEARCH_CORRECTION_PARAMETERS)>
```

Attributes

The DID_YOU_MEAN element has no attributes.

Sub-elements

The following table provides a brief overview of the DID_YOU_MEAN sub-element.

Sub-element	Brief description
SEARCH_CORRECTION_PARAMETERS	Specifies general spelling correction parameters for Did You Mean and automatic spelling correction.

MEMBER_NAME

The MEMBER_NAME element specifies the name of a property or dimension that is part of a SEARCH_INTERFACE.

For information on search interfaces, see "About Search Interfaces" in the *Endeca MDEX Engine Basic Development Guide*.

DTD

```
<!ELEMENT MEMBER_NAME (#PCDATA)>
<!ATTLIST MEMBER_NAME
  RELEVANCE_RANK      CDATA      #IMPLIED
  SNIPPET_SIZE        CDATA      "0"
  >
```

Attributes

The following sections describe the MEMBER_NAME element's attributes.

RELEVANCE_RANK

RELEVANCE_RANK is an unsigned integer that specifies the relevance rank of a match on the specified dimension or property.

SNIPPET_SIZE

The presence of SNIPPET_SIZE enables snippetting for a MEMBER_NAME and the value of SNIPPET_SIZE specifies maximum number of words a snippet can contain. Omitting this attribute or setting its value equal to zero disables snippetting. For more information, see "Using Snippetting in Record Searches" in the *Endeca Basic Development Guide*.

Sub-elements

The MEMBER_NAME element has no sub-elements.

Example

In the following example, four properties are listed in MEMBER_NAME elements, each with its own relevance rank.

```
<SEARCH_INTERFACE CROSS_FIELD_BOUNDARY="NEVER"
  CROSS_FIELD_RELEVANCE_RANK="0"
  DEFAULT_REL_RANK_STRATEGY="All" NAME="All">
  <MEMBER_NAME RELEVANCE_RANK="4">P_WineType</MEMBER_NAME>
  <MEMBER_NAME RELEVANCE_RANK="3">P_Name</MEMBER_NAME>
  <MEMBER_NAME RELEVANCE_RANK="2">P_Winery</MEMBER_NAME>
  <MEMBER_NAME RELEVANCE_RANK="1">P_Description</MEMBER_NAME>
</SEARCH_INTERFACE>
```

PARTIAL_MATCH

The PARTIAL_MATCH element specifies if partial query matches should be supported for the SEARCH_INTERFACE that contains this element.

For details about searching and search modes, see "About Search Modes" in the *Endeca MDEX Engine Basic Development Guide*.

DTD

```
<!ELEMENT PARTIAL_MATCH EMPTY>
<!ATTLIST PARTIAL_MATCH
  MIN_WORDS_INCLUDED      CDATA      #IMPLIED
  MAX_WORDS OMITTED      CDATA      #IMPLIED
>
```

Attributes

The following sections describe the PARTIAL_MATCH element's attributes.

MIN_WORDS_INCLUDED

Specifies that search results match at least this number of terms in the search query. This value must be an integer greater than zero. The default value of this attribute is one.

MAX_WORDS OMITTED

Specifies the maximum number of query terms that may be ignored in the search query. This value must be a non-negative integer. If set to zero or left unspecified, any number of words may be omitted (i.e., there is no maximum). The default value of this attribute is two.

Sub-elements

The PARTIAL_MATCH element has no sub-elements.

Example

In this example, the search interface is subject to partial matching in which at least two of the words in the search query are included, and no more than one is omitted.

```
<SEARCH_INTERFACE CROSS_FIELD_BOUNDARY="ALWAYS"
  CROSS_FIELD_RELEVANCE_RANK="0"
  DEFAULT_RELRANK_STRATEGY="AllPhrase" NAME="AllPhrase">
<MEMBER_NAME RELEVANCE_RANK="2">P_Body</MEMBER_NAME>
<MEMBER_NAME RELEVANCE_RANK="1">P_Description</MEMBER_NAME>
<PARTIAL_MATCH MAX_WORDS OMITTED="1" MIN_WORDS INCLUDED="2" />
</SEARCH_INTERFACE>
```

SEARCH_CORRECTION_PARAMETERS

A SEARCH_CORRECTION_PARAMETERS element specifies general spelling correction parameters for Did You Mean and automatic spelling correction.

For more information about spelling corrections, see "Using Spelling Correction and Did You Mean" in the *Endeca Advanced Development Guide*.

DTD

```
<!ELEMENT SEARCH_CORRECTION_PARAMETERS EMPTY>
<!ATTLIST SEARCH_CORRECTION_PARAMETERS
  HITS_THRESHOLD      CDATA      #IMPLIED
  HITS_GAIN_THRESHOLD CDATA      #IMPLIED
  SPELLING_SCORE_THRESHOLD CDATA      #IMPLIED
  MAX_SUGGESTIONS_RETURNED CDATA      #IMPLIED
  MAX_WORDS_TO_REQUEST      CDATA      #IMPLIED
  MAX_WORDS_TO_USE        CDATA      #IMPLIED
  WORD_BREAK_ANALYSIS    (TRUE | FALSE) #IMPLIED
```

CROSS_FIELD	(TRUE FALSE)	#IMPLIED
>		

Attributes

The following sections describe the SEARCH_CORRECTION_PARAMETERS element's attributes.

HITS_THRESHOLD

Specifies the maximum number of hits for which Did You Mean suggestions should be generated. When a very large number of hits are returned, computing the Did You Mean alternatives may be computationally expensive. The default value is 20.

HITS_GAIN_THRESHOLD

Specifies the minimum percentage gain in hits in order to consider an alternative valid. The default value is 10%. This value should be a decimal number between 0.0 and 1.0.

SPELLING_SCORE_THRESHOLD

Specifies the threshold correction score for words used by the Did You Mean engine. The default value is 150.

MAX_SUGGESTIONS_RETURNED

Specifies the maximum number of per-word spelling corrections to compute for each term in the search query. The default value is 3.

MAX_WORDS_TO_REQUEST

Specifies the maximum number of per-word spelling corrections to request from the spelling engine for each term in the search query. The default value is 10.

MAX_WORDS_TO_USE

Specifies the maximum number of highest-scored per-word spelling suggestions to use from among the available suggestions in the spelling engine. The default value is 10.

WORD_BREAK_ANALYSIS

Specifies whether Did You Mean considers alternate word separation points for the query in order to generate suggestions for spelling correction. For example, if a user searches for "Homemade cookies" then the engine may also consider separations like "Home made cookies." The default value is TRUE.

CROSS_FIELD

Specifies that cross-property suggestions should be allowed and that they should be counted as matches when evaluating the frequencies of suggestions. Normally, suggestions must match results in a single property or dimension value.

Sub-elements

The SEARCH_CORRECTION_PARAMETERS element has no sub-elements.

SEARCH_INTERFACE

The SEARCH_INTERFACE is a named collection of dimensions and/or properties.

Both dimensions and properties can co-exist in a SEARCH_INTERFACE. The dimensions and/or properties in the group are specified in MEMBER_NAME elements.

If a property or dimension is not included in any SEARCH_INTERFACE element, then an implicit SEARCH_INTERFACE element is created with the same name as the property or dimension and that single property or dimension as its only member. The value for the CROSS_FIELD_RELEVANCE_RANK is set to 0.

DTD

```
<!ELEMENT SEARCH_INTERFACE
  ( MEMBER_NAME+
  , PARTIAL_MATCH?
  , AUTO_SUGGEST?
  , DID_YOU_MEAN?
  )
>
<!ATTLIST SEARCH_INTERFACE
  NAME          CDATA      #REQUIRED
  DEFAULT_RELRANK_STRATEGY CDATA      #IMPLIED
  CROSS_FIELD_RELEVANCE_RANK CDATA      #IMPLIED
  CROSS_FIELD_BOUNDARY      (ALWAYS
                            |ON_FAILURE
                            |NEVER)
  STRICT_PHRASE_MATCH      (TRUE | FALSE) #IMPLIED
>
```

Attributes

The following sections describe the SEARCH_INTERFACE element's attributes.

NAME

A unique name for this search interface.

DEFAULT_RELRANK_STRATEGY

For record search, a default relevance scoring function assigned to a SEARCH_INTERFACE. If you are working in Endeca Developer Studio and have applied ranking modules to a search interface, this attribute is populated with a strategy based on the name of the search interface in question. For example, if your search interface is called Flavors, the DEFAULT_RELRANK_STRATEGY attribute has the value "Flavors_strategy".

CROSS_FIELD_RELEVANCE_RANK

Specifies the relevance rank score for cross-field matches. The value should be an unsigned 32-bit integer. The default value for CROSS_FIELD_RELEVANCE_RANK is 0.

CROSS_FIELD_BOUNDARY

Specifies when the search engine should try to match search queries across dimension/property boundaries, but within the members of the SEARCH_INTERFACE. If its value is set to ON_FAILURE, then the search engine will only try to match queries across dimension/property boundaries if it fails to find any match within a single dimension/property. If its value is set to ALWAYS, then the engine will always look for matches across dimension/property boundaries, in addition to matches within a dimension/property.

By default, the MDEX Engine will not look across boundaries for matches.

STRICT_PHRASE_MATCH

Specifies that the MDEX Engine should interpret a query strictly when comparing white space in the query with punctuation in the source text. If set to FALSE, partial word tokens connected in the source text by punctuation can be matched to a phrase query where the partial tokens are separated by spaces instead of matching punctuation. The default value of this attribute is TRUE.

Sub-elements

The following table provides a brief overview of the SEARCH_INTERFACE sub-elements.

Sub-element	Brief description
MEMBER_NAME	Specifies the name of a property or dimension that is part of a SEARCH_INTERFACE.
PARTIAL_MATCH	Specifies if partial query matches should be supported for the SEARCH_INTERFACE that contains this element.
AUTO_SUGGEST	Specifies how to configure automatic spelling correction for either record searches or dimension searches.
DID_YOU_MEAN	Specifies how to configure explicit alternatives for search terms as a part of spelling correction.

Example

This example establishes a search interface called AllFields, which contains four members.

```
<SEARCH_INTERFACE CROSS_FIELD_BOUNDARY="NEVER"
    CROSS_FIELD_RELEVANCE_RANK="0"
    DEFAULT_RELRANK_STRATEGY="All" NAME="AllFields">
    <MEMBER_NAME RELEVANCE_RANK="4">P_WineType</MEMBER_NAME>
    <MEMBER_NAME RELEVANCE_RANK="3">P_Name</MEMBER_NAME>
    <MEMBER_NAME RELEVANCE_RANK="2">P_Winery</MEMBER_NAME>
    <MEMBER_NAME RELEVANCE_RANK="1">P_Description</MEMBER_NAME>
</SEARCH_INTERFACE>
```

Spell_config.xml elements

The Spell_config.xml file specifies which spelling correction dictionary, or combination of dictionaries, and which languages the MDEX Engines uses to provide spelling correct suggestions.

The root element of Spell_config.xml is SPELL_CONFIG. Through its sub-element SPELL_ENGINE, you can configure the aspell or espell dictionary combinations and corresponding language codes. For more information, see "Using Spelling Correction and Did You Mean" in the *Endeca MDEX Engine Advanced Development Guide*.



Note: You cannot create this file in Developer Studio. Use a text editor to create it, then place the file in the directory where the project XML files reside.

ASPELL

The ASPELL element instructs the MDEX Engine to correct queries using the Aspell dictionary.

Aspell is a phonetic spelling dictionary that corrects only English-like words, that includes letters A through Z but excludes accented letters and numbers. The English-like set includes a large subset of words in languages other than English, for example German and Spanish. If desired, you can set the LANGUAGES attribute to restrict corrections to English only.

DTD

```
<!ELEMENT ASPELL EMPTY>
<!ATTLIST ASPELL
    LANGUAGES      CDATA      " "
>
```

Attributes

The following section describes the ASPELL element's attribute.

LANGUAGES

Specifies a two-character language code that restricts spelling correction to a particular language. For the ASPELL element, the meaningful value of this attribute is `en` for English. If no value is provided, Aspell corrects using relevant English-like words.

Sub-elements

The ASPELL element has no sub-elements.

Example

This example uses the Aspell dictionary to correct English queries but not queries in other languages.

```
<SPELL_CONFIG>
    <SPELL_ENGINE>
        <ASPELL LANGUAGES="en" />
    </SPELL_ENGINE>
</SPELL_CONFIG>
```

DICT_PER_LANGUAGE

The DICT_PER_LANGUAGE element creates a separate dictionary for each language.

Having separate dictionaries allows you to restrict spelling correction suggestions on a per-language basis. This is useful if, for example, you do not want English queries to produce spelling suggestions in Spanish.

DTD

```
<!ELEMENT DICT_PER_LANGUAGE (ESPELL) >
<!ATTLIST DICT_PER_LANGUAGE
    LANGUAGES      CDATA      " "
>
```

Attributes

The following section describes the DICT_PER_LANGUAGE element's attribute.

LANGUAGES

Specifies a language code or a comma-separated list of language codes that restrict spelling correction to a particular language or a group of languages. ISO 639 lists the valid language codes.

Common examples include the following: `en` for English, `es` for Spanish, `fr` for French, `de` for German, `ja` for Japanese, and `ko` for Korean. Note that Chinese has two available codes: `zh-CN` for simplified Chinese and `zh-TW` for traditional Chinese. If no value is provided, Espell corrects using any relevant language.

Sub-elements

The following table provides a brief overview of the DICT_PER_LANGUAGE sub-element.

Sub-element	Brief description
ESPELL	Instructs the MDEX Engine to correct queries using the Espell dictionary.

Example

The following example creates separate spelling dictionaries for each language, using Aspell for English and Espell for all other languages.

```
<SPELL_CONFIG>
  <SPELL_ENGINE>
    <FIRST_DICT>
      <ASPELL LANGUAGES="en" />
      <DICT_PER_LANGUAGE>
        <ESPELL/>
      </DICT_PER_LANGUAGE>
    </FIRST_DICT>
  </SPELL_ENGINE>
</SPELL_CONFIG>
```

ESPELL

The ESPELL element instructs the MDEX Engine to correct queries using the Espell dictionary.

Espell is a non-phonetic spelling dictionary that corrects for words in any language including non-alphabetic words (i.e., words containing numbers or punctuation). If desired, you can set the LANGUAGES attribute to restrict corrections to a specific language or a set of languages.

DTD

```
<!ELEMENT ESPELL EMPTY>
<!ATTLIST ESPELL
  LANGUAGES CDATA      "">
```

Attributes

The following section describes the ESPELL element's attribute.

LANGUAGES

Specifies a language code or a comma-separated list of language codes that restrict spelling correction to a particular language or a group of languages. ISO 639 lists the valid language codes.

Common examples include the following: `en` for English, `es` for Spanish, `fr` for French, `de` for German, `ja` for Japanese, and `ko` for Korean. Note that Chinese has a two available codes: `zh-CN` for simplified Chinese and `zh-TW` for traditional Chinese. If no value is provided, Espell corrects using any relevant language.

Sub-elements

The ESPELL element has no sub-elements.

Example

This example uses Espell to correct queries to English, Spanish, or French but no other languages.

```
<SPELL_CONFIG>
  <SPELL_ENGINE>
    <ESPELL LANGUAGES="en,es,fr" />
  </SPELL_ENGINE>
</SPELL_CONFIG>
```

FIRST_DICT

The FIRST_DICT element combines two or more spelling dictionaries.

The FIRST_DICT element also allows the first dictionary that can correct a word to provide spelling corrections. The remaining dictionaries do not process the word. For example, if you have Aspell as the first dictionary and Espell as the second, then words that Aspell cannot correct are handed to the Espell dictionary. In this configuration, the Espell engine would not process or suggest possible alternatives for any words corrected by Aspell. See the example below.

DTD

```
<!ELEMENT FIRST_DICT
  ( ASPELL
  | ESPELL
  | UNION_DICTS
  | FIRST_DICT
  | DICT_PER_LANGUAGE
  )+
>
<!ATTLIST FIRST_DICT
  LANGUAGES   CDATA      " "
```

Attributes

The following section describes the FIRST_DICT element's attribute.

LANGUAGES

Specifies a language code or a comma-separated list of language codes that restrict spelling correction to a particular language or a group of languages. ISO 639 lists the valid language codes.

Common examples include the following: `en` for English, `es` for Spanish, `fr` for French, `de` for German, `ja` for Japanese, and `ko` for Korean. Note that Chinese has two available codes: `zh-CN` for simplified Chinese and `zh-TW` for traditional Chinese. If no value is provided, Espell corrects using any relevant language.

Sub-elements

The following table provides a brief overview of the FIRST_DICT sub-elements.

Sub-element	Brief description
ASPELL	Instructs the MDEX Engine to correct queries using the Aspell dictionary.
ESPELL	Instructs the MDEX Engine to correct queries using the Espell dictionary.

Sub-element	Brief description
UNION_DICTS	Combines two or more spelling dictionaries and allows each dictionary to process all words for spelling correction.
FIRST_DICT	Combines two or more spelling dictionaries and allows the first dictionary that can correct a word to provide spelling corrections.
dict_per_language	Creates a separate dictionary for each language. This allows you to restrict spelling correction suggestions on a per-language basis.

Example

This example shows Aspell as the first dictionary and Espell as the second. Words that Aspell cannot correct are handed to the Espell dictionary. The Espell engine would not process or suggest possible alternatives for any words corrected by Aspell.

```
<SPELL_CONFIG>
  <SPELL_ENGINE>
    <FIRST_DICT>
      <ASPELL LANGUAGES="en" />
      <dict_per_language>
        <espell/>
      </dict_per_language>
    </FIRST_DICT>
  </SPELL_ENGINE>
</SPELL_CONFIG>
```

SPELL_CONFIG

A SPELL_CONFIG element configures the global use of spelling correction dictionaries and languages for language-specific spelling correction.

DTD

```
<!ELEMENT SPELL_CONFIG
  ( COMMENT?
  , SPELL_ENGINE?
  )
>
```

Attributes

The SPELL_CONFIG elements has no attributes.

Sub-elements

The following table provides a brief overview of the SPELL_CONFIG sub-elements.

Sub-element	Brief description
COMMENT	Associates a comment with a parent element and preserves the comment when the file is rewritten. This element provides an alternative to using inline XML comments of the form <!-- ... -->.
SPELL_ENGINE	Specifies whether to use Aspell, espell, or combinations of the two spelling dictionaries to make spelling corrections.

Example

This example shows Aspell as the first dictionary and Espell as the second. Words that Aspell cannot correct are handed to the Espell dictionary. The Espell engine would not process or suggest possible alternatives for any words corrected by Aspell.

```
<SPELL_CONFIG>
  <SPELL_ENGINE>
    <FIRST_DICT>
      <ASPELL LANGUAGES="en" />
      <DICT_PER_LANGUAGE>
        <ESPELL/>
      </DICT_PER_LANGUAGE>
    </FIRST_DICT>
  </SPELL_ENGINE>
</SPELL_CONFIG>
```

SPELL_ENGINE

A SPELL_ENGINE element specifies whether to use aspell, espell, or combinations of the two spelling dictionaries to make spelling corrections.

There are five possibilities to configure an application's spelling dictionaries:

- ASPELL on its own to correct only English-like words.
- ESPPELL on its own to correct words in any language including non-alphabetic words.
- UNION_DICTS combines the spelling suggestions from two or more occurrences of ASPELL and ESPPELL.
- FIRST_DICT returns suggestions from the first spelling dictionary that can correct a given word.
- DICT_PER_LANGUAGE uses a separate dictionary for each language.

All sub-elements of SPELL_ENGINE have a LANGUAGES attribute that causes the spelling dictionary to correct to the language specified and to ignore words in other languages. For more information, see "Using Spelling Correction and Did You Mean" in the *Endeca MDEX Engine Advanced Development Guide*.

DTD

```
<!ELEMENT SPELL_ENGINE
  ( ASPELL
  | ESPPELL
  | UNION_DICTS
  | FIRST_DICT
  | DICT_PER_LANGUAGE
  )
>
```

Attributes

The SPELL_ENGINE element has no attributes.

Sub-elements

The following table provides a brief overview of the SPELL_ENGINE sub-elements.

Sub-element	Brief description
ASPELL	Instructs the MDEX Engine to correct queries using the Aspell dictionary.
ESPELL	Instructs the MDEX Engine to correct queries using the Espell dictionary.
UNION_DICTS	Combines two or more spelling dictionaries and allows each dictionary to process all words for spelling correction.
FIRST_DICT	Combines two or more spelling dictionaries and allows the first dictionary that can correct a word to provide spelling corrections.
DICT_PER_LANGUAGE	Creates a separate dictionary for each language. This allows you to restrict spelling correction suggestions on a per-language basis.

Example

This example shows Aspell as the first dictionary and Espell as the second. Words that Aspell cannot correct are handed to the Espell dictionary. The Espell engine would not process or suggest possible alternatives for any words corrected by Aspell.

```
<SPELL_CONFIG>
  <SPELL_ENGINE>
    <FIRST_DICT>
      <ASPELL LANGUAGES="en" />
      <DICT_PER_LANGUAGE>
        <ESPELL />
      </DICT_PER_LANGUAGE>
    </FIRST_DICT>
  </SPELL_ENGINE>
</SPELL_CONFIG>
```

UNION_DICTS

The UNION_DICTS element combines two or more spelling dictionaries and allows each dictionary to process all words for spelling correction.

For example, if you union Aspell and Espell, then Aspell processes English-like words, while Espell processes all words. Because the two spell engines have different strengths, this is different behavior from simply letting Espell process all words. For more information, see "Using Spelling Correction and Did You Mean" in the *Endeca MDEX Engine Advanced Development Guide*.

DTD

```
<!ELEMENT UNION_DICTS
  ( ASPELL
  | ESPPELL
  | UNION_DICTS
  | FIRST_DICT
  | DICT_PER_LANGUAGE
  )+
>
<!ATTLIST UNION_DICTS
  LANGUAGES      CDATA      " "
>
```

Attributes

The following section describes the UNION_DICTS element's attribute.

LANGUAGES

Specifies a language code or a comma-separated list of language codes that restrict spelling correction to a particular language or a group of languages. ISO 639 lists the valid language codes.

Common examples include the following: `en` for English, `es` for Spanish, `fr` for French, `de` for German, `ja` for Japanese, and `ko` for Korean. Note that Chinese has two available codes: `zh-CN` for simplified Chinese and `zh-TW` for traditional Chinese. If no value is provided, Espell corrects using any relevant language.

Sub-elements

The following table provides a brief overview of the UNION_DICTS sub-elements.

Sub-element	Brief description
ASPELL	Instructs the MDEX Engine to correct queries using the Aspell dictionary.
ESPELL	Instructs the MDEX Engine to correct queries using the Espell dictionary.
UNION_DICTS	Combines two or more spelling dictionaries and allows each dictionary to process all words for spelling correction.
FIRST_DICT	Combines two or more spelling dictionaries and allows the first dictionary that can correct a word to provide spelling corrections.
DICT_PER_LANGUAGE	Creates a separate dictionary for each language. This allows you to restrict spelling correction suggestions on a per-language basis.

Example

The following example shows a union of Aspell and Espell, where Aspell processes English-like words, while Espell processes all words.

```
<SPELL_CONFIG>
  <SPELL_ENGINE>
    <UNION_DICTS>
      <ASPELL/>
      <ESPELL/>
    </UNION_DICTS>
  </SPELL_ENGINE>
</SPELL_CONFIG>
```

Stemming.xml elements

The Stemming.xml file contains an element for each language that is enabled for stemming.

The stemming feature allows the system to consider alternate forms of individual words as equivalent for the purpose of search query matching. For example, it is often desirable for singular nouns to match their plural equivalents in the searchable text, and vice versa. See "Using Stemming and Thesaurus" in the *Endeca MDEX Engine Advanced Development Guide* for more information.

STEM_CS

Not supported.

STEM_DA

Not supported.

STEM_DE

A STEM_DE element specifies whether German is enabled for stemming.

DTD

```
<!ELEMENT STEM_DE EMPTY>
<!ATTLIST STEM_DE ENABLE (TRUE|FALSE) "FALSE">
<!ATTLIST STEM_DE USE_STATIC_WORDFORMS (TRUE|FALSE) "TRUE">
<!ATTLIST STEM_DE USE_COMPOUND_MATCHING (TRUE|FALSE) "FALSE">
```

Attributes

The following sections describe the STEM_DE element's attributes.

ENABLE

Set to TRUE if the language is enabled for stemming. If the attribute is set to FALSE or if the language's element is not listed in Stemming.xml, then the language is not enabled for stemming.

USE_STATIC_WORDFORMS

If set to TRUE, the stemming feature uses the static word form files shipped with the MDEX Engine package. If set to FALSE, the Indexer generates the word forms file from the corpus, using the dynamic stemming add-in.

USE_COMPOUND_MATCHING

If set to TRUE, the stemming feature is extended to allow matching query words that are subsets of indexed compound words.

Sub-elements

The STEM_DE element has no sub-elements.

Example

This example enables German stemming, enables the use of the static word form files from the MDEX Engine package, and disables the matching of query words that are subsets of indexed compound words.

```
<STEMMING>
  <STEM_DE ENABLE="TRUE" />
  <STEM_DE USE_STATIC_WORDFORMS="TRUE" />
  <STEM_DE USE_COMPOUND_MATCHING="FALSE" />
</STEMMING>
```

STEM_EL

Not supported.

STEM_EN_UK

Not supported.

STEM_EN_US

A STEM_EN_US element specifies whether U.S. English is enabled for stemming.

DTD

```
<!ELEMENT STEM_EN_US EMPTY>
<!ATTLIST STEM_EN_US ENABLE (TRUE|FALSE) "TRUE">
<!ATTLIST STEM_EN_US USE_STATIC_WORDFORMS (TRUE|FALSE) "TRUE">
<!ATTLIST STEM_EN_US USE_COMPOUND_MATCHING (TRUE|FALSE) "FALSE">
```

Attributes

The following sections describe the STEM_EN_US element's attributes.

ENABLE

Set to TRUE if the language is enabled for stemming. If the attribute is set to FALSE or if the language's element is not listed in Stemming.xml, then the language is not enabled for stemming.

USE_STATIC_WORDFORMS

If set to TRUE, the stemming feature uses the static word form files shipped with the MDEX Engine package. If set to FALSE, the Indexer generates the word forms file from the corpus, using the dynamic stemming add-in.

USE_COMPOUND_MATCHING

If set to TRUE, the stemming feature is extended to allow matching query words that are subsets of indexed compound words.

Sub-elements

The STEM_EN_US element has no sub-elements.

Example

This example enables U.S. English stemming, enables the use of the static word form files from the MDEX Engine package, and disables the matching of query words that are subsets of indexed compound words.

```
<STEMMING>
  <STEM_EN_US ENABLE="TRUE" />
  <STEM_EN_US USE_STATIC_WORDFORMS="TRUE" />
  <STEM_EN_US USE_COMPOUND_MATCHING="FALSE" />
</STEMMING>
```

STEM_ES

A STEM_ES element specifies whether Spanish is enabled for stemming.

DTD

```
<!ELEMENT STEM_ES EMPTY>
<!ATTLIST STEM_ES ENABLE (TRUE|FALSE) "FALSE">
<!ATTLIST STEM_ES USE_STATIC_WORDFORMS (TRUE|FALSE) "TRUE">
<!ATTLIST STEM_ES USE_COMPOUND_MATCHING (TRUE|FALSE) "FALSE">
```

Attributes

The following sections describe the STEM_ES element's attributes.

ENABLE

Set to TRUE if the language is enabled for stemming. If the attribute is set to FALSE or if the language's element is not listed in Stemming.xml, then the language is not enabled for stemming.

USE_STATIC_WORDFORMS

If set to TRUE, the stemming feature uses the static word form files shipped with the MDEX Engine package. If set to FALSE, the Indexer generates the word forms file from the corpus, using the dynamic stemming add-in.

USE_COMPOUND_MATCHING

If set to TRUE, the stemming feature is extended to allow matching query words that are subsets of indexed compound words.

Sub-elements

The STEM_ES element has no sub-elements.

Example

This example enables Spanish stemming, enables the use of the static word form files from the MDEX Engine package, and disables the matching of query words that are subsets of indexed compound words.

```
<STEMMING>
  <STEM_ES ENABLE="TRUE" />
  <STEM_ES USE_STATIC_WORDFORMS="TRUE" />
  <STEM_ES USE_COMPOUND_MATCHING="FALSE" />
</STEMMING>
```

STEM_FR

A STEM_FR element specifies whether French is enabled for stemming.

DTD

```
<!ELEMENT STEM_FR EMPTY>
<!ATTLIST STEM_FR ENABLE (TRUE|FALSE) "FALSE">
<!ATTLIST STEM_FR USE_STATIC_WORDFORMS (TRUE|FALSE) "TRUE">
<!ATTLIST STEM_FR USE_COMPOUND_MATCHING (TRUE|FALSE) "FALSE">
```

Attributes

The following sections describe the STEM_FR element's attributes.

ENABLE

Set to TRUE if the language is enabled for stemming. If the attribute is set to FALSE or if the language's element is not listed in Stemming.xml, then the language is not enabled for stemming.

USE_STATIC_WORDFORMS

If set to TRUE, the stemming feature uses the static word form files shipped with the MDEX Engine package. If set to FALSE, the Indexer generates the word forms file from the corpus, using the dynamic stemming add-in.

USE_COMPOUND_MATCHING

If set to TRUE, the stemming feature is extended to allow matching query words that are subsets of indexed compound words.

Sub-elements

The STEM_FR element has no sub-elements.

Example

This example enables French stemming, enables the use of the static word form files from the MDEX Engine package, and disables the matching of query words that are subsets of indexed compound words.

```
<STEMMING>
  <STEM_FR ENABLE="TRUE" />
  <STEM_FR USE_STATIC_WORDFORMS="TRUE" />
  <STEM_FR USE_COMPOUND_MATCHING="FALSE" />
</STEMMING>
```

STEM_HU

Not supported.

STEM_IT

A STEM_IT element specifies whether Italian is enabled for stemming.

DTD

```
<!ELEMENT STEM_IT EMPTY>
<!ATTLIST STEM_IT ENABLE (TRUE | FALSE) "FALSE">
<!ATTLIST STEM_IT USE_STATIC_WORDFORMS (TRUE | FALSE) "TRUE">
<!ATTLIST STEM_IT USE_COMPOUND_MATCHING (TRUE | FALSE) "FALSE">
```

Attributes

The following sections describe the STEM_IT element's attributes.

ENABLE

Set to TRUE if the language is enabled for stemming. If the attribute is set to FALSE or if the language's element is not listed in Stemming.xml, then the language is not enabled for stemming.

USE_STATIC_WORDFORMS

If set to TRUE, the stemming feature uses the static word form files shipped with the MDEX Engine package. If set to FALSE, the Indexer generates the word forms file from the corpus, using the dynamic stemming add-in.

USE_COMPOUND_MATCHING

If set to TRUE, the stemming feature is extended to allow matching query words that are subsets of indexed compound words.

Sub-elements

The STEM_IT element has no sub-elements.

Example

This example enables Italian stemming, enables the use of the static word form files from the MDEX Engine package, and disables the matching of query words that are subsets of indexed compound words.

```
<STEMMING>
  <STEM_IT ENABLE="TRUE" />
  <STEM_IT USE_STATIC_WORDFORMS="TRUE" />
  <STEM_IT USE_COMPOUND_MATCHING="FALSE" />
</STEMMING>
```

STEM_JP

A STEM_JP element specifies whether Japanese is enabled for stemming.

DTD

```
<!ELEMENT STEM_JP EMPTY>
<!ATTLIST STEM_JP ENABLE (TRUE|FALSE) "FALSE">
<!ATTLIST STEM_JP USE_STATIC_WORDFORMS (TRUE|FALSE) "FALSE">
<!ATTLIST STEM_JP USE_COMPOUND_MATCHING (TRUE|FALSE) "FALSE">
```

Attributes

The following sections describe the STEM_JP element's attributes.

ENABLE

Set to TRUE if the language is enabled for stemming. If the attribute is set to FALSE or if the language's element is not listed in Stemming.xml, then the language is not enabled for stemming.

USE_STATIC_WORDFORMS

If set to TRUE, the stemming feature uses the static word form files shipped with the MDEX Engine package. If set to FALSE, the Indexer generates the word forms file from the corpus, using the dynamic stemming add-in.

USE_COMPOUND_MATCHING

If set to TRUE, the stemming feature is extended to allow matching query words that are subsets of indexed compound words.

Sub-elements

The STEM_JP element has no sub-elements.

Example

This example enables Japanese stemming, enables the use of the static word form files from the MDEX Engine package, and disables the matching of query words that are subsets of indexed compound words.

```
<STEMMING>
  <STEM_JP ENABLE="TRUE" />
  <STEM_JP USE_STATIC_WORDFORMS="TRUE" />
  <STEM_JP USE_COMPOUND_MATCHING="FALSE" />
</STEMMING>
```

STEM_KO

A STEM_KO element specifies whether Korean is enabled for stemming.

DTD

```
<!ELEMENT STEM_KO EMPTY>
<!ATTLIST STEM_KO ENABLE (TRUE|FALSE) "FALSE" >
<!ATTLIST STEM_KO USE_STATIC_WORDFORMS (TRUE|FALSE) "FALSE" >
<!ATTLIST STEM_KO USE_COMPOUND_MATCHING (TRUE|FALSE) "FALSE" >
```

Attributes

The following sections describe the STEM_KO element's attributes.

ENABLE

Set to TRUE if the language is enabled for stemming. If the attribute is set to FALSE or if the language's element is not listed in Stemming.xml, then the language is not enabled for stemming.

USE_STATIC_WORDFORMS

If set to TRUE, the stemming feature uses the static word form files shipped with the MDEX Engine package. If set to FALSE, the Indexer generates the word forms file from the corpus, using the dynamic stemming add-in.

USE_COMPOUND_MATCHING

If set to TRUE, the stemming feature is extended to allow matching query words that are subsets of indexed compound words.

Sub-elements

The STEM_KO element has no sub-elements.

Example

This example enables Korean stemming, enables the use of the static word form files from the MDEX Engine package, and disables the matching of query words that are subsets of indexed compound words.

```
<STEMMING>
  <STEM_KO ENABLE="TRUE" />
  <STEM_KO USE_STATIC_WORDFORMS="TRUE" />
```

```
<STEM_KO USE_COMPOUND_MATCHING="FALSE" />
</STEMMING>
```

STEM_NL

A STEM_NL element specifies whether Dutch is enabled for stemming.

DTD

```
<!ELEMENT STEM_NL EMPTY>
<!ATTLIST STEM_NL ENABLE (TRUE|FALSE) "FALSE">
<!ATTLIST STEM_NL USE_STATIC_WORDFORMS (TRUE|FALSE) "TRUE">
<!ATTLIST STEM_NL USE_COMPOUND_MATCHING (TRUE|FALSE) "FALSE">
```

Attributes

The following sections describe the STEM_NL element's attributes.

ENABLE

Set to TRUE if the language is enabled for stemming. If the attribute is set to FALSE or if the language's element is not listed in Stemming.xml, then the language is not enabled for stemming.

USE_STATIC_WORDFORMS

If set to TRUE, the stemming feature uses the static word form files shipped with the MDEX Engine package. If set to FALSE, the Indexer generates the word forms file from the corpus, using the dynamic stemming add-in.

USE_COMPOUND_MATCHING

If set to TRUE, the stemming feature is extended to allow matching query words that are subsets of indexed compound words.

Sub-elements

The STEM_NL element has no sub-elements.

Example

This example enables Dutch stemming, enables the use of the static word form files from the MDEX Engine package, and disables the matching of query words that are subsets of indexed compound words.

```
<STEMMING>
  <STEM_NL ENABLE="TRUE" />
  <STEM_NL USE_STATIC_WORDFORMS="TRUE" />
  <STEM_NL USE_COMPOUND_MATCHING="FALSE" />
</STEMMING>
```

STEM_PL

Not supported.

STEM_PT

A STEM_PT element specifies whether Portuguese is enabled for stemming.

DTD

```
<!ELEMENT STEM_PT EMPTY>
<!ATTLIST STEM_PT ENABLE (TRUE|FALSE) "FALSE">
<!ATTLIST STEM_PT USE_STATIC_WORDFORMS (TRUE|FALSE) "TRUE">
<!ATTLIST STEM_PT USE_COMPOUND_MATCHING (TRUE|FALSE) "FALSE">
```

Attributes

The following sections describe the STEM_PT element's attributes.

ENABLE

Set to TRUE if the language is enabled for stemming. If the attribute is set to FALSE or if the language's element is not listed in Stemming.xml, then the language is not enabled for stemming.

USE_STATIC_WORDFORMS

If set to TRUE, the stemming feature uses the static word form files shipped with the MDEX Engine package. If set to FALSE, the Indexer generates the word forms file from the corpus, using the dynamic stemming add-in.

USE_COMPOUND_MATCHING

If set to TRUE, the stemming feature is extended to allow matching query words that are subsets of indexed compound words.

Sub-elements

The STEM_PT element has no sub-elements.

Example

This example enables Portuguese stemming, enables the use of the static word form files from the MDEX Engine package, and disables the matching of query words that are subsets of indexed compound words.

```
<STEMMING>
  <STEM_PT ENABLE="TRUE" />
  <STEM_PT USE_STATIC_WORDFORMS="TRUE" />
  <STEM_PT USE_COMPOUND_MATCHING="FALSE" />
</STEMMING>
```

STEM_XX

Not supported.

STEM_ZH_CN

A STEM_ZH_CN element specifies whether Chinese (simplified) is enabled for stemming.

DTD

```
<!ELEMENT STEM_ZH_CN EMPTY>
<!ATTLIST STEM_ZH_CN ENABLE (TRUE|FALSE) "FALSE">
<!ATTLIST STEM_ZH_CN USE_STATIC_WORDFORMS (TRUE|FALSE) "FALSE">
<!ATTLIST STEM_ZH_CN USE_COMPOUND_MATCHING (TRUE|FALSE) "FALSE">
```

Attributes

The following sections describe the STEM_ZH_CN element's attributes.

ENABLE

Set to TRUE if the language is enabled for stemming. If the attribute is set to FALSE or if the language's element is not listed in Stemming.xml, then the language is not enabled for stemming.

USE_STATIC_WORDFORMS

If set to TRUE, the stemming feature uses the static word form files shipped with the MDEX Engine package. If set to FALSE, the Indexer generates the word forms file from the corpus, using the dynamic stemming add-in.

USE_COMPOUND_MATCHING

If set to TRUE, the stemming feature is extended to allow matching query words that are subsets of indexed compound words.

Sub-elements

The STEM_ZH_CN element has no sub-elements.

Example

This example enables Chinese (simplified) stemming, enables the use of the static word form files from the MDEX Engine package, and disables the matching of query words that are subsets of indexed compound words.

```
<STEMMING>
  <STEM_ZH_CN ENABLE="TRUE" />
  <STEM_ZH_CN USE_STATIC_WORDFORMS="TRUE" />
  <STEM_ZH_CN USE_COMPOUND_MATCHING="FALSE" />
</STEMMING>
```

STEM_ZH_TW

A STEM_ZH_TW element specifies whether Chinese (traditional) is enabled for stemming.

DTD

```
<!ELEMENT STEM_ZH_TW EMPTY>
<!ATTLIST STEM_ZH_TW ENABLE (TRUE|FALSE) "FALSE">
<!ATTLIST STEM_ZH_TW USE_STATIC_WORDFORMS (TRUE|FALSE) "FALSE">
<!ATTLIST STEM_ZH_TW USE_COMPOUND_MATCHING (TRUE|FALSE) "FALSE">
```

Attributes

The following sections describe the STEM_ZH_TW element's attributes.

ENABLE

Set to TRUE if the language is enabled for stemming. If the attribute is set to FALSE or if the language's element is not listed in Stemming.xml, then the language is not enabled for stemming.

USE_STATIC_WORDFORMS

If set to TRUE, the stemming feature uses the static word form files shipped with the MDEX Engine package. If set to FALSE, the Indexer generates the word forms file from the corpus, using the dynamic stemming add-in.

USE_COMPOUND_MATCHING

If set to TRUE, the stemming feature is extended to allow matching query words that are subsets of indexed compound words.

Sub-elements

The STEM_ZH_TW element has no sub-elements.

Example

This example enables Chinese (traditional) stemming, enables the use of the static word form files from the MDEX Engine package, and disables the matching of query words that are subsets of indexed compound words.

```
<STEMMING>
  <STEM_ZH_TW ENABLE="TRUE" />
  <STEM_ZH_TW USE_STATIC_WORDFORMS="TRUE" />
  <STEM_ZH_TW USE_COMPOUND_MATCHING="FALSE" />
</STEMMING>
```

Stop_words.xml elements

The Stop_words.xml file contains words that should be eliminated from a query before it is processed by the MDEX Engine.

Each stop is specified in a STOP_WORD element.

STOP_WORD

The STOP_WORD element identifies words that should be eliminated from a query before it is processed.

Examples of common stop words include the words "the" and "of".

DTD

```
<!ELEMENT STOP_WORD (#PCDATA)>
```

Attributes

The STOP_WORD element has no attributes.

Sub-elements

The STOP_WORD element has no sub-elements.

Example

This example shows a common set of stop words.

```
<STOP_WORDS>
  <STOP_WORD>a</STOP_WORD>
  <STOP_WORD>an</STOP_WORD>
  <STOP_WORD>of</STOP_WORD>
  <STOP_WORD>the</STOP_WORD>
</STOP_WORDS>
```

STOP_WORDS

A STOP_WORDS element specifies the stop words enabled in your application.

Each stop word is represented by a STOP_WORD element.

DTD

```
<!ELEMENT STOP_WORDS
  ( COMMENT?
    , STOP_WORD*
  )
>
```

Attributes

The STOP_WORDS element has no attributes.

Sub-elements

The following table provides a brief overview of the STOP_WORDS sub-elements.

Sub-element	Brief description
COMMENT	Associates a comment with a parent element and preserves the comment when the file is rewritten. This element provides an alternative to using inline XML comments of the form <!-- ... -->.
STOP_WORD	Identifies words that should be eliminated from a query before it is processed.

Example

This example shows a common set of stop words.

```
<STOP_WORDS>
  <STOP_WORD>a</STOP_WORD>
  <STOP_WORD>an</STOP_WORD>
  <STOP_WORD>of</STOP_WORD>
  <STOP_WORD>the</STOP_WORD>
</STOP_WORDS>
```

Studio_project.esp elements

The Studio_project.esp file contains the elements for a Developer Studio project.

A Developer Studio project has a project file that is typically the name of your project followed by an Endeca Studio Project (.esp) extension. This file tracks the other files used in the project.

PROJECT_FILE

A PROJECT_FILE element specifies an individual project file of a Developer Studio project.

All the project files in a project constitute the instance configuration. If a project file is missing, Developer Studio throws an error when attempting to load the project.

DTD

```
<!ELEMENT PROJECT_FILE EMPTY>
<!ATTLIST PROJECT_FILE
  TYPE      CDATA  #REQUIRED
  %url;
  HIGHEST_ID CDATA  #IMPLIED
>
```

Attributes

The following sections describe the PROJECT_FILE element's attributes.

TYPE

Specifies the root element for the project file.

URL

Specifies the file name element for the project file.

HIGHEST_ID

Identifies the highest rule group ID number that has ever been used in your project's defined rule groups.

Sub-elements

The PROJECT_FILE element has no sub-elements.

Example

This example shows three of the PROJECT_FILE elements in the wine demo project file.

```
<STUDIO_PROJECT APP_VERSION="5.1" NAME="Sample Wine Pipeline" VERSION="500">
  <PROJECT_MANAGER_CONFIG APPLICATION="wine" FORGE_OP_CONFIG="--pruneAutoGen"
    PORT="8888" URL="localhost" />
  <PROJECT_PIPELINE URL="pipeline.epx" />
  <PROJECT_FILE TYPE="ANALYTICS_CONFIG" URL="wine.analytics_config.xml" />
  <PROJECT_FILE TYPE="DERIVED_PROPS" URL="wine.derived_props.xml" />
  <PROJECT_FILE TYPE="DIMENSION_GROUPS" URL="wine.dimension_groups.xml" />
  ...
</STUDIO_PROJECT>
```

PROJECT_MANAGER_CONFIG

A PROJECT_MANAGER_CONFIG element specifies the host and port of Endeca Workbench and application name this project is associated with.

DTD

```
<!ELEMENT PROJECT_MANAGER_CONFIG EMPTY>
<!ATTLIST PROJECT_MANAGER_CONFIG
  %url;
  PORT          CDATA  #REQUIRED
  APPLICATION    CDATA  #IMPLIED
  FORGE_OP_CONFIG CDATA  #IMPLIED
  ENE_OP_CONFIG   CDATA  #IMPLIED
  AENE_OP_CONFIG  CDATA  #IMPLIED
  INDEXER_OP_CONFIG CDATA  #IMPLIED
>
```

Attributes

The following sections describe the PROJECT_MANAGER_CONFIG element's attributes. Note that the FORGE_OP_CONFIG, ENE_OP_CONFIG, AENE_OP_CONFIG, and INDEXER_OP_CONFIG attributes are no longer used.

URL

Specifies the host on which Endeca Workbench is running.

PORT

Specifies the port number on which on Endeca Workbench listens.

APPLICATION

Specifies the application in Endeca Workbench that the Developer Studio project is associated with.

Sub-elements

The PROJECT_MANAGER_CONFIG element has no sub-elements.

Example

This example shows some elements of the wine demo project file.

```
<STUDIO_PROJECT APP_VERSION="6.0"
  NAME="Sample Wine Pipeline" VERSION="600">
  <PROJECT_MANAGER_CONFIG APPLICATION="wine" PORT="8888"
    URL="localhost"/>
  <PROJECT_PIPELINE URL="pipeline.epx"/>
  <PROJECT_FILE TYPE="ANALYTICS_CONFIG" URL="wine.analytics_config.xml"/>
  <PROJECT_FILE TYPE="DERIVED_PROPS" URL="wine.derived_props.xml"/>
  <PROJECT_FILE TYPE="DIMENSION_GROUPS" URL="wine.dimension_groups.xml"/>
  ...
</STUDIO_PROJECT>
```

PROJECT_PIPELINE

A PROJECT_PIPELINE element specifies the name of the project's pipeline.epx file.

DTD

```
<!ELEMENT PROJECT_PIPELINE EMPTY>
<!ATTLIST PROJECT_PIPELINE
  %url;
  TYPE  CDATA  #IMPLIED
>
```

Attributes

The following sections describe the PROJECT_PIPELINE element's attributes.

URL

Specifies the file name element for the pipeline.epx file

TYPE

Specifies the root element for the pipeline.epx file.

Sub-elements

The PROJECT_PIPELINE element has no sub-elements.

Example

This example shows the PROJECT_PIPELINE element of the wine demo project file.

```
<STUDIO_PROJECT APP_VERSION="6.0"
  NAME="Sample Wine Pipeline" VERSION="600">
  <PROJECT_MANAGER_CONFIG APPLICATION="wine" PORT="8888"
    URL="localhost"/>
  <PROJECT_PIPELINE URL="pipeline.epx"/>
  <PROJECT_FILE TYPE="ANALYTICS_CONFIG" URL="wine.analytics_config.xml"/>
  ...
</STUDIO_PROJECT>
```

STUDIO_PROJECT

A STUDIO_PROJECT element specifies the name of a project and version information for Developer Studio.

DTD

```
<!ELEMENT STUDIO_PROJECT
  ( COMMENT?
    , PROJECT_MANAGER_CONFIG
    , PROJECT_RESOURCE_CONFIG?
    , PROJECT_PIPELINE+
    , PROJECT_NAV_CONFIG?
    , PROJECT_FILE*
  )
>
<!ATTLIST STUDIO_PROJECT
  NAME          CDATA      #REQUIRED
  VERSION       CDATA      #IMPLIED
  APP_VERSION   CDATA      #IMPLIED
  TYPE          CDATA      #IMPLIED
>
```

Attributes

The following sections describe the STUDIO_PROJECT element's attributes.

NAME

Specifies the project name.

VERSION

Specifies the version of Developer Studio used to create the project.

APP_VERSION

Specifies the version of Developer Studio used to create the project.

Sub-elements

The following table provides a brief overview of the STUDIO_PROJECT sub-elements.

Sub-element	Brief description
COMMENT	Associates a comment with a parent element and preserves the comment when the file is rewritten. This element provides an alternative to using inline XML comments of the form <!-- ... -->.
PROJECT_MANAGER_CONFIG	Specifies the host, port, and command line options that Developer Studio passes to Endeca Workbench.
PROJECT_RESOURCE_CONFIG	Deprecated.
PROJECT_PIPELINE	Specifies the name of the project's pipeline.epx file.
PROJECT_NAV_CONFIG	Deprecated.
PROJECT_FILE	Specifies an individual project file of a Developer Studio project.

Example

This example shows some of the sub-elements contain in the STUDIO_PROJECT element of the wine demo project file.

```
<STUDIO_PROJECT APP_VERSION="6.0"
  NAME="Sample Wine Pipeline" VERSION="600">
  <PROJECT_MANAGER_CONFIG APPLICATION="wine" PORT="8888"
    URL="localhost"/>
  <PROJECT_PIPELINE URL="pipeline.epx"/>
  <PROJECT_FILE TYPE="ANALYTICS_CONFIG" URL="wine.analytics_config.xml"/>
  <PROJECT_FILE TYPE="DERIVED_PROPS" URL="wine.derived_props.xml"/>
  <PROJECT_FILE TYPE="DIMENSION_GROUPS" URL="wine.dimension_groups.xml"/>
  ...
</STUDIO_PROJECT>
```

Thesaurus.xml elements

The Thesaurus.xml file contains thesaurus entries for your application.

Thesaurus entries provide a means to account for alternate forms of a user's query. These entries provide concept-level mappings between words and phrases. See "Using Stemming and Thesaurus" in the *Endeca MDEX Engine Advanced Development Guide* for more information.

THESAURUS

A THESAURUS element contains the term equivalence mappings for an application.

THESAURUS is the root element for all thesaurus entries.

Note that the order of sub-elements within THESAURUS is significant. You should add sub-elements in the order in which they are listed in the DTD section. For example, THESAURUS_ENTRY sub-elements appear before THESAURUS_ENTRY_ONEWAY. See the example below.

DTD

```
<!ELEMENT THESAURUS
  ( COMMENT?
  , THESAURUS_ENTRY*
  , THESAURUS_ENTRY_ONEWAY*
  )
>
```

Attributes

The THESAURUS element has no attributes.

Sub-elements

The following table provides a brief overview of the THESAURUS sub-elements.

Sub-element	Brief description
COMMENT	Associates a comment with a parent element and preserves the comment when the file is rewritten. This element provides an alternative to using inline XML comments of the form <!-- ... -->.
THESAURUS_ENTRY	Indicates a set of word forms (contained in THESAURUS_FORM elements) that are equivalent.
THESAURUS_ENTRY_ONEWAY	Specifies single-direction equivalency mappings.

Example

This example shows the thesaurus entries for an application.

```
<THESAURUS>
  <THESAURUS_ENTRY>
    <THESAURUS_FORM>france</THESAURUS_FORM>
    <THESAURUS_FORM>french</THESAURUS_FORM>
  </THESAURUS_ENTRY>
  <THESAURUS_ENTRY_ONEWAY>
    <THESAURUS_FORM_FROM>Red wine</THESAURUS_FORM_FROM>
    <THESAURUS_FORM_TO>Merlot</THESAURUS_FORM_TO>
    <THESAURUS_FORM_TO>Shiraz</THESAURUS_FORM_TO>
    <THESAURUS_FORM_TO>Bordeaux</THESAURUS_FORM_TO>
  </THESAURUS_ENTRY_ONEWAY>
</THESAURUS>
```

THESAURUS_ENTRY

The THESAURUS_ENTRY element indicates a set of word forms that are equivalent.

The word forms are contained in THESAURUS_FORM elements. A search for any of these forms (including stemming-matched versions) returns hits for all of the forms.

DTD

```
<!ELEMENT THESAURUS_ENTRY (THESAURUS_FORM+)>
```

Attributes

The THESAURUS_ENTRY element has no attributes.

Sub-elements

The following table provides a brief overview of the THESAURUS_ENTRY sub-element.

Sub-element	Brief description
THESAURUS_ENTRY	Indicates a set of word forms that are equivalent.

Example

In this example, the noun and adjective forms of a word are made equivalent.

```
<THESAURUS>
  <THESAURUS_ENTRY>
    <THESAURUS_FORM>france</THESAURUS_FORM>
    <THESAURUS_FORM>french</THESAURUS_FORM>
  </THESAURUS_ENTRY>
</THESAURUS>
```

THESAURUS_ENTRY_ONEWAY

A THESAURUS_ENTRY_ONEWAY element specifies a single-direction mapping.

Searches for any of the "from" forms (THESAURUS_FORM_FROM elements) also return hits for all of the "to" forms (THESAURUS_FORM_TO elements). The other direction is not enabled; that is, searches for the "to" forms do not return results for either the "from" forms or the other "to" forms.

DTD

```
<!ELEMENT THESAURUS_ENTRY_ONEWAY
  ( THESAURUS_FORM_FROM
  , THESAURUS_FORM_TO+
  )>
```

Attributes

The THESAURUS_ENTRY_ONEWAY element has no attributes.

Sub-elements

The following table provides a brief overview of the THESAURUS_ENTRY_ONEWAY sub-elements.

Sub-element	Brief description
THESAURUS_FORM_FROM	Specifies the "from" form in a one-way word mapping.

Sub-element	Brief description
THESAURUS_FORM_TO	Specifies the "to" form in a one-way word mapping.

Example

In this example, searches for Red wine would return hits for Red wine as well as for Merlot, Shiraz, and Bordeaux. Since the equivalence is one-way, more specific searches such as Shiraz or Bordeaux would not return results for the more general concept Red wine.

```
<THESAURUS_ENTRY_ONEWAY>
  <THESAURUS_FORM_FROM>Red wine</THESAURUS_FORM_FROM>
  <THESAURUS_FORM_TO>Merlot</THESAURUS_FORM_TO>
  <THESAURUS_FORM_TO>Shiraz</THESAURUS_FORM_TO>
  <THESAURUS_FORM_TO>Bordeaux</THESAURUS_FORM_TO>
</THESAURUS_ENTRY_ONEWAY>
```

THESAURUS_FORM

The THESAURUS_FORM element contains a word form that is used by the THESAURUS_ENTRY element to set an equivalence.

DTD

```
<!ELEMENT THESAURUS_FORM (#PCDATA)>
```

Attributes

The THESAURUS_FORM element has no attributes.

Sub-elements

The THESAURUS_FORM element has no sub-elements.

Example

In this example, the noun and adjective forms of a word are made equivalent.

```
<THESAURUS>
  <THESAURUS_ENTRY>
    <THESAURUS_FORM>france</THESAURUS_FORM>
    <THESAURUS_FORM>french</THESAURUS_FORM>
  </THESAURUS_ENTRY>
</THESAURUS>
```

THESAURUS_FORM_FROM

The THESAURUS_FORM_FROM element provides the "from" form within a THESAURUS_ENTRY_ONEWAY element.

DTD

```
<!ELEMENT THESAURUS_FORM_FROM (#PCDATA)>
```

Attributes

The THESAURUS_FORM_FROM element has no attributes.

Sub-elements

The THESAURUS_FORM_FROM element has no sub-elements.

Example

In this example, searches for `home theater` would return hits for `home theater` as well as for `stereo` and `television`. Because the equivalence is one-way, more specific searches such as `stereo` or `television` would not return results for the more general concept `home theater`.

```
<THESAURUS_ENTRY_ONEWAY>
  <THESAURUS_FORM_FROM>home theater</THESAURUS_FORM_FROM>
  <THESAURUS_FORM_TO>stereo</THESAURUS_FORM_TO>
  <THESAURUS_FORM_TO>television</THESAURUS_FORM_TO>
</THESAURUS_ENTRY_ONEWAY>
```

THESAURUS_FORM_TO

The THESAURUS_FORM_TO element provides the "to" form within a THESAURUS_ENTRY_ONEWAY element.

DTD

```
<!ELEMENT THESAURUS_FORM_TO (#PCDATA)>
```

Attributes

The THESAURUS_FORM_TO element has no attributes.

Sub-elements

The THESAURUS_FORM_TO element has no sub-elements.

Example

In this example, searches for `home theater` would return hits for `home theater` as well as for `stereo` and `television`. Because the equivalence is one-way, more specific searches such as `stereo` or `television` would not return results for the more general concept `home theater`.

```
<THESAURUS_ENTRY_ONEWAY>
  <THESAURUS_FORM_FROM>home theater</THESAURUS_FORM_FROM>
  <THESAURUS_FORM_TO>stereo</THESAURUS_FORM_TO>
  <THESAURUS_FORM_TO>television</THESAURUS_FORM_TO>
</THESAURUS_ENTRY_ONEWAY>
```

Index

A

about this document 11
analytics_config.xml
 about 11
ASPELL 144
AUTO_SUGGEST 139

B

BOUND 24

C

CLUSTERS 112
COMMENT 11
common.dtd
 COMMENT 11
 compression 12
Common.dtd
 CONFIG 13
 DIMENSION_ID 14
 DIMNAME 14
 DVAL_ID 15
 DVAL_PATH 16
 KEY_DIMENSION 16
 LOG 17
 PHRASE 18
 PROFILE 19
 PROP 19
 PROPNAM 20
 PVAL 20
 RECORD_GROUP 20
 RECORD_ID 21
 RECORD_INDEX 21
compression 12
CONFIG 13

D

DERIVED_PROP 22
DERIVED_PROPS 23
Derived_props.xml
 about 22
 DERIVED_PROP 22
 DERIVED_PROPS 23
DICT_PER_LANGUAGE 145
DID_YOU_MEAN 139
DIMENSION 25
DIMENSION_ADAPTER 49
DIMENSION_GROUP 32
DIMENSION_GROUPS 33

Dimension_groups.xml
 about 32
 DIMENSION_GROUP 32
 DIMENSION_GROUPS 33
DIMENSION_ID 14
DIMENSION_IMPORTS 48
DIMENSION_INPUTS 97
DIMENSION_NODE 27
DIMENSION_REF 34
DIMENSION_REFS 35
Dimension_refs.xml
 about 34
 DIMENSION_REF 34
 DIMENSION_REFS 35
DIMENSION_SERVER 51
DIMENSION_SOURCE 52
DIMENSIONS 26
Dimensions.xml
 about 23
 BOUND 24
 DIMENSION 25
 DIMENSION_NODE 27
 DIMENSIONS 26
 DVAL 28
 LBOUND 29
 NUM_DVALS 30
 SYN 30
 UBOUND 31
 DIMNAME 14
 DIMSEARCH_CONFIG 36
Dimsearch_config.xml
 about 36
 DIMSEARCH_CONFIG 36
DIMSEARCH_HIERARCHY 38
DIMSEARCH_INDEX 38
Dimsearch_index.xml
 about 37
 DIMSEARCH_HIERARCHY 38
 DIMSEARCH_INDEX 38
 DVAL 28
 DVAL_ID 15
 DVAL_ID_LIMITS 53
 DVAL_PATH 16
 DVAL_RANK 40
 DVAL_RANKS 41
 Dval_ranks.xml
 about 40
 DVAL_RANK 40
 DVAL_RANKS 41
 DVAL_REF 42
 DVAL_REFS 43
 Dval_refs.xml
 about 42
 DVAL_REF 42

Dval_refs.xml (*continued*)
 DVAL_REFS 43
 DYNAMIC_RANKING 114

E

ESPELL 146
 EXPRBODY 54
 EXPRESSION 54
 EXPRNODE 56
 externaldimensions.xml, about 44

F

FIRST_DICT 147

I

ID_SERVER 57
 INDEXER_ADAPTER 58
 INPUT 98
 introduction 11

J

JAVA_MANIPULATOR 61
 JOIN_ENTRY 62

K

KEY_DIMENSION 16
 KEY_LANGUAGE 44
 Key_props.xml, about 44

L

LANGUAGES 45
 Languages.xml
 about 44
 KEY_LANGUAGE 44
 LANGUAGES 45
 LBOUND 29
 LOG 17

M

MEMBER_NAME 140

N

NUM_DVALS 30

P

PARTIAL_MATCH 140
 PASS_THROUGH 63
 PERL_MANIPULATOR 66

PERL_METHOD 68
 PHRASE 18
 PHRASE_ADDITIONS 47
 PHRASES 46
 Phrases.xml
 about 46
 DIMENSION_IMPORTS 48
 PHRASE_ADDITIONS 47
 PHRASES 46
 PIPELINE 70
 Pipeline.epx
 DVAL_ID_LIMITS 53
 EXPRBODY 54
 Pipeline.exp
 about 48
 DIMENSION_ADAPTER 49
 DIMENSION_SERVER 51
 DIMENSION_SOURCE 52
 EXPRESSION 54
 EXPRNODE 56
 ID_SERVER 57
 INDEXER_ADAPTER 58
 JAVA_MANIPULATOR 61
 JOIN_ENTRY 62
 PASS_THROUGH 63
 PERL_MANIPULATOR 66
 PERL_METHOD 68
 PIPELINE 70
 PROP_MAPPER 72
 PROP_MAPPING_DIM 74
 PROP_MAPPING_NONE 76
 PROP_MAPPING_PROP 76
 RECORD_ADAPTER 78
 RECORD_ASSEMBLER 84
 RECORD_CACHE 85
 RECORD_JOIN 87
 RECORD_MANIPULATOR 88
 RECORD_SOURCE 89
 ROLLOVER 90
 TRANSFORMER 91
 UPDATE_ADAPTER 92
 POSITIONAL_INDEX 136
 PRECEDENCE_RULE 94
 PRECEDENCE_RULES 95
 Precedence_rules.xml
 about 94
 PRECEDENCE_RULE 94
 PRECEDENCE_RULES 95
 PROFILE 19
 PROFILES 96
 Profiles.xml
 about 96
 PROFILES 96
 PROJECT 99
 PROJECT_FILE 163
 PROJECT_MANAGER_CONFIG 164
 PROJECT_PIPELINE 165
 Project.xml
 about 97
 DIMENSION_INPUTS 97

Project.xml (*continued*)

- INPUT 98
- PROJECT 99
- RECORD_INPUTS 100
- PROP 19
- PROP_MAPPER 72
- PROP_MAPPING_DIM 74
- PROP_MAPPING_NONE 76
- PROP_MAPPING_PROP 76
- PROP_REF 101
- PROP_REFS 101
- Prop_refs.xml
 - about 100
 - PROP_REF 101
 - PROP_REFS 101
- PROPNAMEx 20
- PVAL 20

R

- RECORD_ADAPTER 78
- RECORD_ASSEMBLER 84
- RECORD_CACHE 85
- RECORD_FILTER 102
- Record_filter.xml
 - about 102
 - RECORD_FILTER 102
- RECORD_GROUP 20
- RECORD_ID 21
- RECORD_ID_PROP 103
- Record_id_prop.xml
 - about 103
 - RECORD_ID_PROP 103
- RECORD_INDEX 21
- RECORD_INPUTS 100
- RECORD_JOIN 87
- RECORD_MANIPULATOR 88
- RECORD_SORT 104
- RECORD_SORT_CONFIG 105
- Record_sort_config.xml
 - about 104
 - RECORD_SORT 104
 - RECORD_SORT_CONFIG 105
- RECORD_SOURCE 89
- RECORD_SPEC 106
- Record_spec.xml
 - about 106
 - RECORD_SPEC 106
- RECSEARCH_CONFIG 107
- Recsearch_config.xml
 - about 107
 - RECSEARCH_CONFIG 107
- RECSEARCH_INDEX 109
- RECSEARCH_INDEXES 110
- Recsearch_indexes.xml
 - about 109
 - RECSEARCH_INDEX 109
 - RECSEARCH_INDEXES 110

- Refinement_config.xml
 - about 112
 - CLUSTERS 112
 - DYNAMIC_RANKING 114
 - REFINEMENTS 115
 - REFINEMENTS_CONFIG 116
 - STATS 117
- REFINEMENTS 115
- REFINEMENTS_CONFIG 116
- RELRANK_APPROXPHRASE 119
- RELRANK_EXACT 119
- RELRANK_FIELD 120
- RELRANK_FIRST 120
- RELRANK_FREQ 121, 126
- RELRANK_GLOM 121
- RELRANK_INTERP 122
- RELRANK_MAXFIELD 122
- RELRANK_MODULE 123
- RELRANK_NTERMS 124
- RELRANK_NUMFIELDS 124
- RELRANK_PHRASE 125
- RELRANK_SPELL 126
- RELRANK_STATIC 127
- RELRANK_STRATEGIES 127
- Relrank_strategies.xml
 - about 119
 - RELRANK_APPROXPHRASE 119
 - RELRANK_EXACT 119
 - RELRANK_FIELD 120
 - RELRANK_FIRST 120
 - RELRANK_FREQ 121, 126
 - RELRANK_GLOM 121
 - RELRANK_INTERP 122
 - RELRANK_MAXFIELD 122
 - RELRANK_MODULE 123
 - RELRANK_NTERMS 124
 - RELRANK_NUMFIELDS 124
 - RELRANK_PHRASE 125
 - RELRANK_SPELL 126
 - RELRANK_STATIC 127
 - RELRANK_STRATEGIES 127
 - RELRANK_STRATEGY 128
 - RELRANK_WFREQ 130
- RELRANK_STRATEGY 128
- RELRANK_WFREQ 130
- RENDER 131
- RENDER_CONFIG 132
- Render_config.xml
 - about 131
 - RENDER 131
 - RENDER_CONFIG 132
- ROLLOVER 90
- ROLLUP 133
- ROLLUPS 134
- Rollups.xml
 - about 133
 - ROLLUP 133
 - ROLLUPS 134

S

SEARCH_CHAR 134
 SEARCH_CHARS 135
 Search_chars.xml
 about 134
 SEARCH_CHAR 134
 SEARCH_CHARS 135
 SEARCH_CORRECTION_PARAMETERS 141
 SEARCH_INDEX 137
 SEARCH_INTERFACE 142
 Search_interface.xml
 about 138
 AUTO_SUGGEST 139
 DID_YOU_MEAN 139
 MEMBER_NAME 140
 PARTIAL_MATCH 140
 SEARCH_CORRECTION_PARAMETERS 141
 SEARCH_INTERFACE 142
 Searchindex.xml
 about 136
 POSITIONAL_INDEX 136
 SEARCH_INDEX 137
 WILDCARD_INDEX 137
 SPELL_CONFIG 148
 Spell_config.exp
 about 144
 Spell_config.xml
 ASPELL 144
 DICT_PER_LANGUAGE 145
 ESPELL 146
 FIRST_DICT 147
 SPELL_CONFIG 148
 SPELL_ENGINE 149
 UNION_DICTS 150
 SPELL_ENGINE 149
 STATS 117
 STEM_DE 152
 STEM_EN_US 153
 STEM_ES 154
 STEM_FR 155
 STEM_IT 155
 STEM_JP 156
 STEM_KO 157
 STEM_NL 158
 STEM_PT 159
 STEM_ZH_CN 160
 STEM_ZH_TW 160
 Stemming.xml
 about 151
 STEM_DE 152
 STEM_EN_US 153
 STEM_ES 154
 STEM_FR 155

Stemming.xml (continued)

STEM_IT 155
 STEM_JP 156
 STEM_KO 157
 STEM_NL 158
 STEM_PT 159
 STEM_ZH_CN 160
 STEM_ZH_TW 160
 STOP_WORD 161
 STOP_WORDS 162
 Stop_words.xml
 about 161
 STOP_WORD 161
 STOP_WORDS 162
 STUDIO_PROJECT 166
 Studio_project.esp
 PROJECT_FILE 163
 PROJECT_MANAGER_CONFIG 164
 PROJECT_PIPELINE 165
 STUDIO_PROJECT 166
 Studio_project.xml
 about 163
 SYN 30

T

THESAURUS 167
 THESAURUS_ENTRY 168
 THESAURUS_ENTRY_ONEWAY 168
 THESAURUS_FORM 169
 THESAURUS_FORM_FROM 170
 THESAURUS_FORM_TO 170
 Thesaurus.xml
 about 166
 THESAURUS 167
 THESAURUS_ENTRY 168
 THESAURUS_ENTRY_ONEWAY 168
 THESAURUS_FORM 169
 THESAURUS_FORM_FROM 170
 THESAURUS_FORM_TO 170
 TRANSFORMER 91

U

UBOUND 31
 UNION_DICTS 150
 UPDATE_ADAPTER 92

W

welcome 11
 WILDCARD_INDEX 137