

Oracle Tuxedo Application Runtime for Batch

Reference Guide

11g Release 1 (11.1.1.3.0)

December 2011

ORACLE®

Copyright © 2011, Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this software or related documentation is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, the following notice is applicable:

U.S. GOVERNMENT RIGHTS Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, duplication, disclosure, modification, and adaptation shall be subject to the restrictions and license terms set forth in the applicable Government contract, and, to the extent applicable by the terms of the Government contract, the additional rights set forth in FAR 52.227-19, Commercial Computer Software License (December 2007). Oracle USA, Inc., 500 Oracle Parkway, Redwood City, CA 94065.

This software is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications which may create a risk of personal injury. If you use this software in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure the safe use of this software. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software in dangerous applications.

Oracle is a registered trademark of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners.

This software and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

Contents

Introduction

Z/OS JCL in the Batch Runtime Environment

Introduction to z/OS JCL in the Batch Runtime Environment	2-1
z/OS JCL Cards in the Batch Runtime Environment	2-1
JCL Card Equivalence Table	2-2
DCB Parameter of DD Statement	2-13
SYSOUT Parameter of DD Statement	2-15
DATACLAS Parameter of DD Statement	2-15
RESTART Parameter of JOB Statement	2-15
In-Stream File	2-15
Concatenation of Files	2-16
Override of Files	2-16
Execution of External Sysin.	2-16
General Utility Commands Equivalence Table	2-16
Sort Utilities	2-20
Sort Utilities Equivalence Tables	2-20
DB2 Utilities	2-21

Oracle Tuxedo Application Runtime for Batch Functions

Introduction to the Batch Runtime Commands	3-1
Emulating z/OS JCL Logic and Architecture	3-1
EJR Syntax	3-3

Tools for Managing the Execution of Jobs	3-4
Oracle Tuxedo Application Runtime for Batch Functions.	3-6
Naming Convention	3-6
Reference Page Command Syntax	3-7
Reference	3-9

Tuxedo Job Enqueueing Service (TuxJES)

genjesprofile	4-2
artjesadmin	4-2
ARTJESADM	4-8
ARTJESCONV	4-10
ARTJESINITIATOR	4-10
ARTJESPURGE.	4-12
TuxJES Queue System.	4-12
The TuxJES Queue Creation Script	4-13
Recommended /Q Creation Values	4-13
TuxJES User Substitution	4-14
Terms.	4-14
Job Owner Designation in Different Scenarios.	4-14
Permissions of Job Operations	4-15
Enabling User Substitution in TuxJES	4-16

Introduction

The Oracle Tuxedo Application Runtime for Batch normalizes Korn shell script formats by proposing a script model in which the different execution phases are clearly identified, and provides the Tuxedo Job Enqueueing Service (TuxJES), which emulates the major functions of Mainframe JES2.

This guide consists of three main parts:

- The first part describes the equivalencies that exist between JCL cards, general utility commands and sorts on the one hand and the Batch Runtime functions on the other.
- The second part describes how the Korn shell scripts are structured to reproduce a JCL type processing of jobs. The different functions of the Batch Runtime that are used in these scripts are then described in detail.
- The third part describes the servers and utilities for TuxJES.

Introduction

Z/OS JCL in the Batch Runtime Environment

Introduction to z/OS JCL in the Batch Runtime Environment

This section describes how to find equivalents for z/OS JCL statements in the target environment. Some of these equivalents point to the Batch Runtime functions, other equivalents may rely directly on UNIX or Tuxedo features. In some cases, there may be no equivalent and a work-around solution may be necessary.

It is not the purpose of this document to describe z/OS JCL, for any explanation of JCL statements, please see the [z/OS Internet Library](#).

z/OS JCL Cards in the Batch Runtime Environment

The following tables lists the JCL card parameters and the related command in the Batch Runtime:

In the column “status”, the following abbreviations are used

N.R. means “not relevant”

N.S. means “not supported”

JCL Card Equivalence Table

Table 2-1 JCL Card Equivalences

JCL Card	Parameter	Equivalent in Target Environment	Status
//*		Comments.	supported
/*		In-stream data delimiter	supported
//		End of job	supported
COMMAND			N.S.
CNTL/ENDCNTL			N.R.

Table 2-1 JCL Card Equivalences

JCL Card	Parameter	Equivalent in Target Environment	Status
DD	*	m_FileAssign -i	supported
	ACCODE		N.R.
	AMP		N.R.
	AVGREC		N.R.
	BLKSIZE		N.R.
	BLKSZLIM		N.R.
	CCSID		N.R.
	CHKPT		N.S.
	CNTL		N.R.
	DATA	m_FileAssign	supported
	DATACLAS	see DATACLAS chapter	supported
	DCB	see DCB chapter	supported
	DISP	m_FileAssign -d <DISP option>	supported
	DLM	m_FileAssign -D <delimiter>	supported
	DSID		N.R.
DSNAME	m_FileAssign	supported	

Table 2-1 JCL Card Equivalences

JCL Card	Parameter	Equivalent in Target Environment	Status
DD (continued)	DSNTYPE		N.S.
	DUMMY	m_FileAssign with /dev/null	supported
	DYNAM	m_FileAssign with /dev/null	supported
	EXPDT		N.R.
	FILEDATA		N.R.
	FREE		N.R.
	KEYLEN	m_FileAssign -k	supported
	KEYOFF	m_FileAssign -k	supported
	LABEL		N.R.
	LGSTREAM		N.R.
	LIKE	m_FileAssign -s	supported
	LRECL	m_FileAssign -r	supported
	MGMTCLAS		N.R.
	MSVGP		N.R.
	PATH		N.R.
	PATHDISP		N.R.
	PATHMODE		N.R.
	PATHOPTS		N.R.
	PROTECT		N.R.
	QNAME		N.R.
RECFM	m_FileAssign -r	supported	
RECORDG	m_FileAssign -t	supported	

Table 2-1 JCL Card Equivalences

JCL Card	Parameter	Equivalent in Target Environment	Status
DD (continued)	REFDD		N.S.
	RETPD		N.S.
	RLS		N.R.
	SECMODEL		N.R.
	SPACE		N.R.
	STORCLAS		N.R.
	SUBSYS		N.S.
	TERM		N.R.
	UNIT		N.R.
	VOLUME		N.R.

Table 2-1 JCL Card Equivalences

JCL Card	Parameter	Equivalent in Target Environment	Status
DD : Printing parameters	BURST		N.S.
	CCSID		N.R.
	CHARS		N.S.
	COPIES	m_OutputAssign -c	supported
	DEST	m_OutputAssign -d	supported
	FCB		N.S.
	FLASH		N.S.
	HOLD	m_OutputAssign -H	supported
	MODIFY		N.S.
	OUTLIM		N.S.
	OUTPUT	m_OutputAssign -o	supported
	SEGMENT		N.R.
	SPIN		N.S.
	SYSOUT	see SYSOUT chapter	supported
UCS		N.S.	
DD: Special statements	JOBLIB	m_JobLibset	supported
	STEPLIB	m_StepLibset	supported
	SYSABEND		N.S.
	SYSMDUMP		N.S.
	SYSUDUMP		N.S.
	SYSCHK		N.S.
	SYSIN	m_FileAssign	supported
	SYSCKEOV		N.S.

Table 2-1 JCL Card Equivalences

JCL Card	Parameter	Equivalent in Target Environment	Status
EXEC	ACCT		N.S.
	ADDRSPC		N.R.
	CCSID		N.R.
	COND	m_CondExec	supported
	DPRTY		N.R.
	DYNAMNBR		N.R.
	MEMLIMIT		N.R.
	PARM	m_ProgramExec	supported
	PERFORM		N.R.
	PGM	m_ProgramExec	supported
	PROC		supported
	RD		N.S.
	REGION		N.R.
	RLSTMOUT		N.R.
TIME		N.S.	
IF THEN ELSE END		m_CondIf m_CondElse m_CondEndif	supported
INCLUDE	MEMBER	m_ShellInclude	
JCLLIB	ORDER	m_JclLibSet	

Table 2-1 JCL Card Equivalences

JCL Card	Parameter	Equivalent in Target Environment	Status
JOB	<jobname>	m_JobBegin	supported
	<accounting>		N.S.
	<prog.name>		N.S.
	ADDRSPC		N.R.
	BYTES		N.S.
	CARDS		N.R.
	CCSID		N.S.
	CLASS	m_JobBegin -c (with TuxJES).	supported
	COND	m_JobBegin -C	supported
	GROUP		N.R.
	JESLOG		N.S.
	LINES		N.S.
	MEMLIMIT		N.R.
	MSGCLASS		N.S.
	MSGLEVEL		N.S.
	NOTIFY		N.S.
	PAGES		N.S.
	PASSWORD		N.R.
	PERFORM		N.R.
	PRTY	m_JobBegin -p (with TuxJES).	supported
RD		N.S.	

Table 2-1 JCL Card Equivalences

JCL Card	Parameter	Equivalent in Target Environment	Status
JOB (continued)	SECLABEL		N.R.
	SCHENV		N.R.
	TIME		N.S.
	TYPRUN	m_JobBegin -t (with TuxJES)	supported
	USER		N.S.
OUTPUT	ADDRESS		N.S.
	AFPSTATS		N.S.
	BUILDING		N.S.
	BURST		N.S.
	CHARS		N.S.
	CKPTLINE		N.S.
	CKPTPAGE		N.S.
	CKPTSEC		N.S.
	CLASS	m_OutputSet -c	supported
	COLORMAP		N.S.
	COMPACT		N.S.
	COMSETUP		N.S.
	CONTROL		N.S.
	COPIES	m_OutputSet -n	supported
	DATAACK		N.S.
	DEFAULT	m_OutputSet -D	supported
	DEPT		N.S.
	DEST	m_OutputSet -d	supported

Table 2-1 JCL Card Equivalences

JCL Card	Parameter	Equivalent in Target Environment	Status
OUTPUT (continued)	DPAGELBL		N.S.
	DUPLEX		N.S.
	FCB		N.S.
	FLASH		N.S.
	FORMDEF		N.S.
	FORMLEN		N.S.
	FORMS	m_OutputSet -f	supported
	FSSDATA		N.S.
	GROUPID		N.S.
	INDEX		N.S.
	INTRAY		N.S.
	JESDS		N.S.
	LINDEX		N.S.
	LINECT		N.S.
	MAILBCC		N.S.
	MAILCC		N.S.
	MAILFILE		N.S.
	MAILFROM		N.S.
	MAILTO		N.S.
	MODIFY		N.S.
NAME		N.S.	
NOTIFY		N.S.	
OFFSETXB		N.S.	

Table 2-1 JCL Card Equivalences

JCL Card	Parameter	Equivalent in Target Environment	Status
OUTPUT (continued)	OFFSETXF		N.S.
	OFFSETYB		N.S.
	OFFSETYF		N.S.
	OUTBIN		N.S.
	OUTDISP		N.S.
	OVERLAYB		N.S.
	OVERLAYF		N.S.
	OVFL		N.S.
	PAGEDEF		N.S.
	PIMSG		N.S.
	PORTNO		N.S.
	PRMODE		N.S.
	PRTATTRS		N.S.
	PRTEROR		N.S.
	PRTOPTNS		N.S.
	PRTQUEUE		N.S.
	PRTY	m_OutputSet -p	supported
	REPLYTO		N.S.
	RESFMT		N.S.
	RETAINF		N.S.
RETAINS		N.S.	
RETRYL		N.S.	
RETRYT		N.S.	

Table 2-1 JCL Card Equivalences

JCL Card	Parameter	Equivalent in Target Environment	Status
OUTPUT (continued)	ROOM		N.S.
	SYSAREA		N.S.
	THRESHLD		N.S.
	TITLE		N.S.
	TRC		N.S.
	UCS		N.S.
	USERDATA		N.S.
	USERLIB		N.S.
	USERPATH		N.S.
	WRITER	m_OutputSet -w	supported
PROC		m_ProcInclude	supported
in-stream PROC		m_ProcBegin	supported
in-stream PEND		m_ProcEnd	supported
SET		m_SymbolSet	supported
XMIT			N.S.

DCB Parameter of DD Statement

Table 2-2 DCB Parameter of DD Statement

DCB parameter	Equivalent in Target Environment	Status
BFANL		N.R.
BFTEK		N.R.
BLKSIZE		N.R.
BUFIN		N.R.
BUFL		N.R.
BUFMAX		N.R.
BUFNO		N.R.
BUFOFF		N.R.
BUFOUT		N.R.
BUFSIZE		N.R.
CPRI		N.R.
CYLOFL		N.R.
DEN		N.R.
DIAGNS		N.R.
DSORG	<code>m_FileAssign -t</code>	supported
EROPT		N.R.
FUNC		N.R.
GNCPL		N.R.
INTVL		N.R.
IPLTXID		N.R.
KEYLEN	<code>m_FileAssign -k</code>	supported

Table 2-2 DCB Parameter of DD Statement

DCB parameter	Equivalent in Target Environment	Status
LIMCT		N.R.
LRECL	m_FileAssign -r	supported
MODE		N.R.
NCP		N.R.
NTM		N.R.
OPTCD		N.R.
PCI		N.R.
PRTSP		N.R.
RECFM	m_FileAssign -r	supported
RESERVE		N.R.
RKP	m_FileAssign -t	supported
STACK		N.R.
TRESH		N.R.
TRTCH		N.R.

SYSOUT Parameter of DD Statement

Table 2-3 SYSOUT Parameter of DD Statement

SYSOUT parameter	Usage	Equivalent in Target Environment	Status
First parameter	Class	m_OutputAssign -c	supported
Second parameter	INTRDR	m_OutputAssign -w	supported
	SMTP	m_OutputAssign -w	supported
	<writer>	m_OutputAssign -w	supported
Third parameter	Form name	m_OutputAssign -f	supported
	Code name		N.S.

DATACLAS Parameter of DD Statement

The DATACLAS parameter is taken into account at WB JCL level only.

Using the DATACLASS informations, extracted from z/OS, the WB JCL updates the m_FileAssign function (or m_FileBuild from DATACLAS parameter in IDCAMS DEFINE commands).

RESTART Parameter of JOB Statement

Only the Deferred Step Restart type is managed.

The other types, Automatic Restart (Step or Checkpoint) and Deferred Checkpoint Restart, are not managed.

A deferred step restart of a job is caused by coding the function m_JobBegin with the -r parameter containing a job step and by submitting the job again.

In-Stream File

The in-stream files are supported using the m_FileAssign function with the -i parameter.

Concatenation of Files

The concatenation of files (or in-stream files) is supported using the `m_FileAssign` function with the `-C` parameter.

Override of Files

The overriding feature is supported.

Use the `m_FileOverride` function for the files managed by the `m_FileAssign` function.

Use the `m_OutputOverride` function for the files managed by the `m_OutputAssign` function.

Execution of External Sysin

Use the `m_UtilityExec` function in order to execute commands stored in a file .

General Utility Commands Equivalence Table

Table 2-4 General Utility Commands Equivalences

Utility	Command	Equivalent in Target Environment	Status
IDCAMS (modal commands)	IF/THEN/ELSE		supported
	SET		supported
	CANCEL		N.S.
	DO/END		N.S.
	MAXCC		supported
	LASTCC		supported

Table 2-4 General Utility Commands Equivalences

Utility	Command	Equivalent in Target Environment	Status
IDCAMS	ALLOCATE (main parameters)	m_FileBuild	supported
	ALTER NEWNAME	m_FileRename	supported
	ALTER LIBRARYENTRY		N.R.
	ALTER VOLUMEENTRY		N.R.
	BLDINDEX		N.R.
	CREATE LIBRARYENTRY		N.R.
	CREATE VOLUMEENTRY		N.R.
	DCOLLECT		N.S.
	DEFINE ALIAS		N.S.
	DEFINE AIX	m_FileBuild -K	supported
	DEFINE CLUSTER	m_FileBuild	supported
	DEFINE GDG	m_GenDefine	supported
	DEFINE NONVSAM		N.S.
	DEFINE PAGESPACE		N.R.
	DEFINE PATH		N.R.
	DEFINE USERCATALOG		N.R.
	DELETE ALAIS		N.S.
	DELETE AIX	m_FileBuild -R	supported
	DELETE CLUSTER	m_FileDelete	supported
	DELETE GDG	m_FileDelete	supported
DELETE LIBRARYENTRY		N.R.	
DELETE NONVSAM	m_FileDelete	supported	

Table 2-4 General Utility Commands Equivalences

Utility	Command	Equivalent in Target Environment	Status
IDCAMS (continued)	DELETE NVR		N.S.
	DELETE PAGESPACE		N.R.
	DELETE PATH		N.R.
	DELETE TRUENAME		N.S.
	DEL USERCATALOG		N.R.
	DELETE VOLUMEENTRY		N.R.
	DELETE VVR		N.R.
	DIAGNOSE		N.S.
	EXAMINE		N.S.
	EXPORT		N.S.
	EXPORT DISCONNECT		N.R.
	IMPORT		N.S.
	IMPORT CONNECT		N.R.
	LISTCAT		N.S.
	LISTDATA		N.S.
	PRINT	m_FilePrint	supported
	REPRO	m_FileRepro	supported
	SETCACHE		N.R.
SHCDS		N.R.	
VERIFY		N.S.	

Table 2-4 General Utility Commands Equivalences

Utility	Command	Equivalent in Target Environment	Status
IEBCOPY	ALTERMOD		N.R.
	COPY	m_DirCopy	supported
	COPYGRP		N.R.
	COPYMOD		N.R.
	EXCLUDE	m_DirCopy -e	supported
	SELECT	m_DirCopy -s	supported
IEBGENER	With SYSIN DUMMY	m_FileLoad	supported
	GENERATE MEMBER		N.S.
	GENERATE RECORD	m_FileSort	supported
IEFBR14		m_ProgramExec IEFBR14	supported
IEFBR15		m_ProgramExec IEFBR15	supported
PKZIP	Main parameters	m_Pkzip	supported
PKUNZIP	Main parameters	m_Pkunzip	supported
SMTP		m_Smtp	supported
XMITIP		m_SendMail	supported
ZIP390	ACTION : ZIP	m_Pkzip	supported
	ACTION : UNZIP	m_Pkunzip	supported
	ENCRYPT		N.S.
	IFILE		supported
	OFILE		supported
	ARCHIVE		supported
	OVERWRITE		supported

Sort Utilities

Sort Utilities Equivalence Tables

SORT, SORTD, DFSORT, ICEMAN, SYNCSORT

Table 2-5 Sort Utilities Equivalences

Sort Statement	Parameter	Equivalent in Target Environment	MFSORT	SyncSort
SORT		m_FileSort	Supported	Supported
MERGE		m_FileSort	Supported	Supported
OPTION		m_FileSort		
	COPY		Supported	Supported
	SKIPREC		Supported	Supported
	STOPAFT		Supported	Supported
	INCLUDE		Supported	Supported
	OMIT		Supported	Supported
	OUTFILE		Supported	Supported
	OUTREC		Supported	Supported
	END		Supported	Supported
	RECORD		Supported	Supported
	SUM		Supported	Supported

ICETOOL

Table 2-6 ICETOOL Equivalences

Sort Statement	Equivalent in Target Environment	MFSORT	SyncSort
SORT	m_FileSort	supported	supported
COPY	m_FileSort	supported	supported
MERGE	m_FileSort	supported	supported

DB2 Utilities

Only DB2 Connect 9.7 or above is supported.

Table 2-7 DB2 Utilities

Command	Parameter	Equivalent in Target Environment	Oracle	DB2LUW
DSNTEP2	SQL	m_ExecSQL	supported	supported
DSNTEP4	SQL	m_ExecSQL	supported	supported
DSNTIAD	SQL	m_ExecSQL	supported	supported
DSNTIAUL	SQL	m_ExecSQL	supported	supported
	"Unload"	m_DBTableUnload	supported	supported
DSNUTILB	EXEC SQL	m_ExecSQL	supported	supported
	LOAD	m_DBTableLoad	supported	supported
	UNLOAD	m_DBTableUnload	supported	supported

Z/OS JCL in the Batch Runtime Environment

Oracle Tuxedo Application Runtime for Batch Functions

Introduction to the Batch Runtime Commands

This chapter describes:

- The format and rules for using the Batch Runtime Korn shell scripts to run jobs in [Emulating z/OS JCL Logic and Architecture](#).
- The use of the Batch Runtime spawner (EJR) to launch jobs in [EJR Syntax](#).
- The log files and return codes used by the scripts and spawner in [Log File Management](#) and [Return Code Management](#).
- The use of the Batch Runtime COBOL runtime to trap errors and manage database interaction in [COBOL Runtime](#).
- A complete description of the Batch Runtime functions in [Oracle Tuxedo Application Runtime for Batch Functions](#).

Emulating z/OS JCL Logic and Architecture

Oracle Tuxedo Application Runtime for Batch provides a set of high-level functions that simplify script syntax enabling more readable and more easily maintainable Korn shell scripts.

Using these functions ensures consistent services; when used together, execution of one function can be conditional on the value of the return code produced by a preceding function.

A function is generally called directly from a Korn shell script resulting from JCL conversion.

Oracle Tuxedo Application Runtime for Batch Functions

Oracle Tuxedo Application Runtime for Batch normalizes Korn shell script formats by proposing a script model where the different execution phases of a job are clearly identified.

EJR Syntax

Synopsis

```
EJR [-c] [-d regexp] [-e] [-H] [-i] [-j] [-k] [-l] [-L] [-r] [-s] [-t file]
[-v] [-V n] Job
```

Arguments

- c**
Conversion phase (only available with TuxJes).
- d regexp**
Debug mode — with a regular expression (regexp) describing the functions to debug, for example `-d "m_FileLoad"` to debug the `m_FileLoad` function.
- e**
Execution phase (only available with TuxJes).
- H**
Execution stack (use limited to maintenance team).
- i**
Input phase (only available with TuxJes).
- j**
Job identifier (only available with TuxJes).
- k**
Cancel command (only available with TuxJes).
- l**
KSH listing included in log (only available with TuxJes).
- L**
Log directory (without TuxJes).
- r**
JES2 root (only available with TuxJes).
- s**
Sysout directory (without TuxJes).

-t file

Test mode — this option runs the script without executing the different steps. It allows to check the kinematics of the Korn shell script (use limited to maintenance team).

-v

Verbose mode — the execution report is displayed on screen during execution. By default not activated.

-V n

Level mode (0 to 9).

Job

The name of the script to be launched without the .ksh extension.

Tools for Managing the Execution of Jobs

Log File Management

When a script is launched with EJR, a log file is generated. When not using TuxJES, the name of the log file is:

```
JobName_YYYYMMDDHHMMSS_Jobid.log.
```

The log file is created in a directory identified by the MT_LOG environment variable. The contents of this file provide the production team with detailed information about the execution of a job.

When using TuxJES, refer to the related documentation.

Return Code Management

Oracle Tuxedo Application Runtime for Batch uses several return-code variables to manage the result of a function execution and the result of job execution.

Table 3-1 Oracle Tuxedo Application Runtime for Batch Return Codes

Return Code	Description
MT_RC	<p>The Return code for an Oracle Tuxedo Application Runtime for Batch function execution.</p> <ul style="list-style-type: none"> • if MT_RC = Cnnnn, return code OK. • if MT_RC = Unnnn, User abort • if MT_RC= Syyy, System abort
MT_RC_JOB	<p>General return code (for the job) MT_RC_JOB is updated with MT_RC at the end of each phase. It contains the maximum MT_RC value for the job.</p>
MT_RC_ABORT	<p>Value fixed to D0000.</p> <p>The MT_RC return code is compared to this value to determine if the result of the execution was normal or not.</p>
MT_RC_PROGRAM_ABORT	<p>By default 127.</p> <p>Contains the return code from an executable (not applicative COBOL program).</p> <ul style="list-style-type: none"> • from 0 to 127: return code OK. • from 128 to 142: it is a signal SKIL in MT_RC • more than 143: Unnn in MT_RC
MT_RC_STEP_RETURNCODE_{LABEL}	<p>Each phase return code is saved. The variable name contains the phase label. This variable can be used for specific chaining within the script.</p>

COBOL Runtime

A COBOL runtime, `runb`, is provided to initialize the execution context of a user COBOL program before the call for its execution. This runtime is used instead of the standard COBOL runtime.

Oracle Tuxedo Application Runtime for Batch Purpose

- Abort trapping procedure definition (standard: `std_proc_error` and database: `dba_proc_error`). The standard procedure traps COBOL errors and traces them in a log file. The Database procedure executes a rollback function to insure data integrity.
- Database access function tracing management (`mw_dbstat`).
- Database Connection and Disconnection and data integrity control (COMMIT and ROLLBACK) if the program is run (`m_ProgramExec`) with `-b` option.
- COBOL program execution.

DataBase Interaction Management

Oracle Tuxedo Application Runtime for Batch takes care of the Database context usage:

- Initialization: If a COBOL program is executed (`m_ProgramExec`) using the `-b` option, the runtime command, `runb`, connects it to the database according to the `MT_DB_LOGIN` environment variable . It must have the correct value (user name, password and Oracle instance, at least `"/`). It can be used in the TuxJES Security Configuration file and specified when submitting jobs or set as an environment variable. If the configuration file is not specified, the environment variable `MT_DB_LOGIN` value is used.
- Termination: Depending on the program return code, the Batch Runtime executes a COMMIT (`MT_RC_JOB = 0`) or a ROLLBACK (`MT_RC_JOB != 0`), then disconnects from the database.

Testing the Validity of a Script (non-exec mode)

Tip: This feature is reserved for the maintenance team.

Using the `-t` argument, it is possible to run the KSH script without executing the internal functions. The `-t` argument allows a script to be checked (for example a newly-developed script) and verify the chaining of the different phases.

Oracle Tuxedo Application Runtime for Batch Functions

Naming Convention

The names of the Batch Runtime functions respect the following format:

prefix_ObjectAction

Where:

prefix_

m specifies an external function.

mi specifies an internal function.

Object

is the type of object on which the function is used and

Action

is the action to be executed on the object.

Examples include:

- **m_FileAssign**
- **m_FileBuild**
- **m_RcTest**
- **m_ProgramExec**

Reference Page Command Syntax

Unless otherwise noted, commands described in the Synopsis section of a reference page accept options and other arguments according to the following syntax and should be interpreted as explained below.

name [**-option . . .**] [**cmdarg . . .**]

where **name** is the name of an executable file and **option** is a string of one of the following two types: **noargletter . . .** or **argletter optarg [, . . .]**

An option is always preceded by a "-".

noargletter

A single letter representing an option that requires no option-argument. More than one noargletter can be grouped after a "-".

optarg

A character string that satisfies a preceding argletter. Multiple optargs following a single argletter must be separated by commas, or separated by white space and enclosed in quotes.

cmdarg

A pathname (or other command argument) that represents an operand of the command.

-

(dash) By itself means that additional arguments are provided in the standard input.

--

(two dashes) Means that what follows are arguments for a subordinate program.

[]

Surrounding an option or cmdarg, mean that the option or argument is not required.

{ }

Surrounding cmdargs that are separated by an or sign, mean that one of the choices must be selected if the associated option is used.

"OR" argument

...

Means that multiple occurrences of the option or cmdarg are permitted.

Reference

The Oracle Tuxedo Application Runtime for Batch Reference Guide describes, in alphabetic order, shell-level functions delivered with the Batch Runtime software.

The following functions are described:

Table 3-2 Batch Runtime Functions

Functions		
m_CondElse	m_FileLoad	m_OutputSet
m_CondEnd	m_FileOverride	m_PhaseBegin
m_CondExec	m_FilePrint	m_PhaseEnd
m_CondIf	m_FileRepro	m_ProcBegin
m_DBTableLoad	m_FileSort	m_ProcEnd
m_DirCreate	m_FileRename	m_ProcInclude
m_DirDelete	m_GenCommit	m_ProgramExec
m_DirRename	m_GenDefine	m_RcSet
m_ExecSQL	m_GenRollback	m_ShellInclude
m_FileAssign	m_JclLibSet	m_StepLibSet
m_FileBuild	m_JobBegin	m_SymbolDefault
m_FileClrData	m_JobEnd	m_SymbolSet
m_FileDelete	m_JobLibSet	m_UtilityExec
m_FileEmpty	m_OutputAssign	
m_FileExist	m_OutputOverride	

Overview

The functions correspond to the interface (API) between the shell script and the Batch Runtime executable. Some scripts, such as m_JclibSet, are used only in the conversion stage and are not present in the extended script that is available for execution.

m_CondElse

Name

m_CondElse — Else of a condition.

Synopsis

m_CondElse

Description

This function marks the alternative part of a [m_CondIf](#) function.

Options

No parameters.

m_CondEnd

Name

m_CondEnd - End of a condition

Synopsis

m_CondEnd

Description

This function ends the previous IF condition.

Options

No parameters.

m_CondExec

Name

m_CondExec — conditional execution (for a program or procedure).

Synopsis

```
m_CondExec condexp [condexp...]
```

Description

Conditional execution. If condition is true, the remaining command in the current step is ignored. Each condition expression contains either, EVEN, ONLY or a value, operator[,step] condition. An m_CondExec statement may contain several condition expressions and this association specifies a logical "OR" of the different conditions.

Options

Condexp [condexp]

Condition expression.

EVEN

Executes step even if previous step ended abnormally.

ONLY

Executes step only if previous step ended abnormally.

value, operator[,step]

Where <step> is any of the previous steps. If the previous step was not executed, the condition is false. When <step> refers to a previous step, replace it with the step label, e.g. "STEPEC01". When <step> refers to a return code of the step in the procedure, replace it with "STEP_PROCNAME_NUM", where "PROCNAME" indicates the name of procedure, and "NUM" indicates the sequence number of the procedure calls.

Examples

```
m_CondExec EVEN
```

To refer to a step:

```
m_CondExec 4,LT,STEPEC01 8,LT,STEPEC02 ONLY
```

To refer to a return code of the step in procedure:

m_CondExec 4,LT,STEP_PROCNAME_NUM ONLY

m_CondIf

Name

m_CondIf - Conditional execution

Synopsis

m_CondIf "condexp [condexp...]"

Description

Executes the condition contained in the "condexp" parameter. Nested levels of "if" conditions are authorized.

Options

"Condexp [condexp]"

Conditional expression.

RC,operator,value

RC indicates a return code.

STEP.RC,operator,value

STEP.RC indicates that the expression tests a return code for a specific STEP.

Operator indicates the operator used for the conditional expression (GT, LT, EQ etc.).

ABEND

ABEND indicates an abend condition occurred.

ABENDCC=number

ABENDCC indicates a system or user completion code.

Examples

m_CondIf " RC, EQ, 3 "

Note: The statements following this m_CondIf statement are executed if the return code is equal to 3.

m_DBTableLoad

Name

m_DBTableLoad – Loads the content of an input file into a database table.

Synopsis

```
m_DBTableLoad -t -i [-e] [-d] [-D]
```

Description

This function executes a command stored in the file which ddname is MT_CTL.

This command is either an SQLLDR command for Oracle or a DB2 LOAD command for DB2LUW according to the target database.

Options

-t <table name>

Mandatory option.
The name of the database table to be loaded.

-i <input flat file>

Mandatory option.
The ddname of the file containing the data to be loaded.

Options for Oracle

-e <error file>

Optional.

SYSERR by default.
The ddname of the error file where are stored the errors during sqlldr command execution.

-d <discard file>

Optional.

SYSERR by default.
The ddname of the file that contains the discarded data during sqlldr command execution.

-D <discard file>

Optional.

999 by default

The maximum number of discarded data.

Options for DB2LUW

-e <error file>

Optional.

<Logfile> by default.

The ddname of the log file used during db2 load command execution.

-d <discard file>

Ignored.

-D <discard file>

Ignored.

Examples

```
m_FileAssign -d OLD DDIN ${DATA}/MYINPUTFILE
m_FileAssign -d SHR MT_CTL ${MT_CTL_FILES}/MYLOADCTL
m_FileAssign -d SHR SYSERR ${[DATA]}/MYSYSERR
m_DBTableLoad -t MYTABLE -i DDIN
```

m_DBTableUnload

Name

m_DBTableUnload – Unloads the content of a database table into a flat file.

Synopsis

```
m_DBTableUnload -t -o
```

Description

This function executes a command stored in the file which ddname is MT_CTL.

This command is either an SQLPLUS command for Oracle or a DB2 EXPORT command for DB2LUW according to the target database.

Options

-t <table name>

Mandatory option.

The name of the database table to be unloaded.

-o <output flat file>

Mandatory option.

The ddname of the file containing the unloaded data.

Examples

```
m_FileAssign -d OLD DDOUT ${DATA}/MYOUTPUTFILE
m_FileAssign -d SHR MT_CTL ${MT_CTL_FILES}/MYUNLOADCTL
m_DBTableUnload -t MYTABLE -o DDOUT
```

m_DirCopy

Name

m_DirCopy – Copies the members of a directory.

Synopsis

```
m_DirCopy [-i] [-o] [-s] [-e]
```

Description

This function copies the members of a directory to another directory.

Options

-i [(**I**{**input**(**input**,**R**)}[**...**]**D**)]

Optional.

Default value : SYSUT1.

input: ddname of the input directory to be copied.

R: specifies that all members to be copied are to replace any identically named members in the output directory. When this option is specified, the ddname and R parameter must be enclosed in a set of parentheses.

Several directories may appear separated by “:”

-o <**output dir**>

Optional.

Default value : SYSUT2.

The ddname of the output directory.

-s <**member list**>

Optional.

Member list to be copied (separated by comma and enclosed in a set of parentheses).

-e <**member list**>

Optional.

Member list to be excluded (separated by comma and enclosed in a set of parentheses).

Examples

Copy of all the members from directory PDS1 to directory SEQ1.

```
m_DirCopy -i PDS1 -o SEQ1
```

Copy of the members A and K from directory PDS1 to directory SEQ1.

```
m_DirCopy -i PDS1 -s "(A,K)" -o SEQ1
```

Copy of all the members except member A from directory PDS1 to directory SEQ1.

```
m_DirCopy -i PDS1 -e A -o SEQ1
```

m_DirCreate

Name

m_DirCreate – Creates a directory.

Synopsis

```
m_DirCreate DirName
```

Description

This function creates a directory.

Options

DirName

The name of the directory to be created.

m_DirDelete

Name

m_DirDelete – Deletes a directory.

Synopsis

```
m_DirDelete DirName
```

Description

This function deletes a directory.

Options

DirName

The name of the directory to be deleted.

m_DirRename

Name

m_DirRename – Renames a directory.

Synopsis

```
m_DirRename OldDirName NewDirName
```

Description

This function renames a directory.

Options

OldDirName

The name of the directory to be renamed.

NewDirName

The new name of the directory to be renamed.

m_ExecSQL

Name

m_ExecSQL — Executes an SQL script.

Synopsis

```
m_ExecSQL [-f] [-o]
```

Description

This function executes an SQL script.

The SQL directives (CREATE TABLE, CREATE INDEX, DELETE, SELECT ...) are in the <inputfile> file. The results will be stored in the file <outputfile>.

Options

-f <inputfile>

The <inputfile> will contain the SQL directives (ddname of the file).

SYSIN is the default value.

-o <outputfile>

The <outputfile> will contain the results (ddname of the file).

SYSPRINT is the default value.

Examples

In the first example, the SQL directives are in the in-stream SYSIN file, the results will be stored in the SYSREC00 file.

```
m_FileAssign -d ,CATLG SYSREC00 ${DATA}/FBACKE.LST.CUMUL
m_FileAssign -i SYSIN
SELECT * FROM PJ01DB2.TABTEST2;
_end
m_ExecSQL -o SYSREC00
```

In the second example, the SQL directives are the file TOW132C.sysin and the results will be printed.

```
m_OutputAssign -c "*" SYSPRINT
m_FileAssign -d SHR SYSIN ${SYSIN}/SYSIN/TOW132C.sysin
m_ExecSQL
```

Note: The DB2 commands are not translated. The user has to verify these commands according to the target data base software.

m_FileAssign

Name

m_FileAssign — Assigns a file.

Synopsis

```
m_FileAssign -i [-C] [-D Delimiter] -g [CUR|ALL [-+np][rang]]
```

```
m_FileAssign -d [-C] [-r RecSize -t Type [-k Key]] -g [CUR|ALL [-+np][rang]]  
ddname [-S dsname]
```

Description

m_FileAssign assigns a file. If assigning a file triggers the creation of a file, the creation process precedes the assign itself.

Specific cases are:

- New files (DISP=NEW parameter).
- Concatenated files (DD cards, where only the first one contains a label). In this case a concatenation is made in a temporary file, the original DSNAMES is replaced by the name of the temporary file.
- Override files (file override in the JCL); a specific assign function [m_FileOverride](#) is used. This function call is implanted in each STEP required, before the execution of the program.
- In the case where a file assign contains a DISP=NEW, DELETE, DELETE parameter, a delete process is added to the end (normal and abnormal) of the step.
- For the DISP=OLD and DISP=PASS options, the file is kept.
- For the DISP=MOD option, the write to the file is made in a temporary intermediary file, then by a copy in EXTEND on the original file.

Options

At least one of the two options “-i” and “-d” must be specified. All other options are optional.

-C <concatenation>

Concatenate this file with the previous dsname for this ddname.

-D <delimiter>

Delimiter of sysin.

-d <DispOption>

This option indicates the DISPosition status of the file in the format:

DISP=(*[status][,normal-termination-disp][,abnormal-termination-disp]*)

Possible combinations are:

```
DISP= (  [NEW]  [,DELETE ]  [,DELETE ] )
        [OLD]  [,KEEP]    [,KEEP ]
        [SHR]  [,PASS]
        [MOD]
        [ANY]
```

The Disp Option indicates the status of the data set at the beginning of a job step and what to do with the data set in the event of normal and abnormal termination of the step.

<status>

The status indicates if an existing data set should be used or a new one created. For existing data sets the status indicates if the data set can be shared with other jobs or used to append records to the end of the data set. the possible values are:

NEW — indicates to create a new unshared data set.

OLD — indicates to use an existing unshared data set.

SHR — indicates to use an existing shared data set.

MOD — indicates an existing unshared data set to add records at the end of file.

An additional status has been added to the traditional z/OS status:

ANY — indicates to use a file in a special mode. The other sub-parameters (<normal-termination-disp> and <abnormal-termination-disp>) are ignored in this case.

Note: OLD and SHR check the file is already existing.

Note: NEW, creation if the file does not exist, abort if the file already exists.

MOD, creation if the file does not exist, continue if the file already exists.

<normal-termination-disp>

This option indicates what to do with a data set when a step ends normally. The possible values are:

DELETE — The data set is no longer needed.

KEEP — The data set is to be kept.

PASS — The data set is to be passed for use by a subsequent step.

(CATLG is managed as KEEP option).

<abnormal-termination-disp>

DELETE — The data set is no longer needed.

KEEP — The data set is to be kept.

(CATLG is managed as KEEP option).

The termination dispositions have default values for each status, the default values are:

NEW: DELETE, DELETE

OLD/SHR/MOD : KEEP, KEEP

Note: PASS is functionally equivalent to KEEP.

-g <argument>

Indicates that the data set is a generation file. The possible values are:

+n: creates the nth new generation file.

-n: accesses the nth previous old generation file.

0: accesses the current generation.

CUR: accesses the current generation.

ALL: concatenates all generation.

-i

Indicates that the data set is a sysin.

-k <key position>+>key length>

Indicates the key characteristics of an indexed file (to be used when file organization is IDX).

-r [<record length-min>-]<record length-max>

Indicates the length characteristics of the record.

For fixed files, only the maximum record length is specified.

For variable files, the minimum and the maximum record lengths are specified.

-S <model file>

(S upper case character)

Names the dsname of a file.

When the disposition mode is NEW, this file is a “model” for the new file to be created.

The characteristics of the new file depends on the characteristics of the “model” file and other parameter given by the `m_FileAssign` function.

-t <file organization>

Indicates the file oraganization type:

SEQ: sequential

LSEQ: line sequential

REL: relative

IDX: indexed

PDS: directory

ddname <InternalFileName>

The logical name of the file as defined in the SELECT statement of the COBOL program.

dsname <ExternalFileName>

Real file name, full path of the file on the disk.

Examples

Example with a shared file:

```
m_FileAssign -d SHR ENTREE ${DATA}/PJ01DDD.BT.QSAM.KBIEI001
```

Example with a sysin and a delimiter:

```
m_FileAssign -i -D FF INPUT
```

```
data input 1
```

```
data input 2
```

```
FF
```

Example with a sysin and continuation:

```
m_FileAssign -i SYSIN
```

```
data input 1
```

```
_end
```

```
##%OPC BEGIN ACTION=INCLUDE
```

Oracle Tuxedo Application Runtime for Batch Functions

```
        m_FileAssign -i -C
data input 2
_end
#%OPC END ACTION=INCLUDE
        m_FileAssign -i -C
data input 3
_end
```

Example with a new file:

```
        m_FileAssign -d NEW -r 188 -t SEQ ENTREE ${DATA}/PJ01DDD.BT.KBIEI001
```

The new file will be a sequential file with a fixed record length of 188 bytes.

Example with a "model" file:

```
        m_FileAssign -d NEW -r 188 -S PJ01.MODEL ENTREE ${DATA}/PJ01.OUTPUT
```

The new file have the characteristics of the file PJ01.MODEL except for the record length given by the "-r" parameter.

m_FileBuild

Name

m_FileBuild — Creates a file.

Synopsis

```
m_FileBuild [-t][-r][-k][-K] [-S]<filename> dsname
```

Description

This function creates a file.

Options

-t <organization>

Type is the organization type of the created file. The possible values are:

SEQ

for a sequential file.

LSEQ

for a line sequential file.

IDX

for an indexed file

REL

for a relative file

Note: The options -r and -k are mandatory for an indexed file.

-r Length

Indicates the record length of the file. This option is mandatory for indexed files.

-k Position+Length

The primary key (mandatory for indexed files)

Position

The first character of the key in relation to the beginning of the record.

Length

The length of the primary key.

-K Position+Length[d]

(K upper case character)

The secondary key indicating that the file contains a secondary key.

Position

The first character of the key in relation to the beginning of the record.

Length

The length of the secondary key.

d

Optional parameter.

Permit duplicates of secondary key.

-S <model file>

(S upper case character)

Names the dsname of a file.

When the disposition mode is NEW, this file is a “model” for the new file to be created.

The characteristics of the new file depends on the characteristics of the “model” file and other parameter given by the m_FileAssign function.

dsname

dsname of the file to create.

Examples

To build an indexed file with no secondary key, the following function builds an indexed file with a record length of 266 bytes. There is no secondary key and the primary key begins in the first character of the record and is six characters long

```
m_FileBuild -t IDX -r 266 -k 1+6 ${DATA}/METAW00.VSAM.CUSTOMER
```

To build a similar indexed file, with in addition, a non-duplicate secondary key in position 20 with a length of 7 the following function can be used:

```
m_FileBuild -t IDX -r 266 -k 1+6 -K 20+7 ${DATA}/METAW00.VSAM.CUSTOMER
```

To build a similar indexed file with a secondary key allowing duplicates in position 20 with a length of 7 the following function can be used:

```
m_FileBuild -t IDX -r 266 -k 1+6 -K 20+7d ${DATA}/METAW.VSAM.CUSTOMER
```

m_FileClrData

Name

m_FileClrData - clears a file.

Synopsis

```
m_FileClrData FileName
```

Description

m_FileClrData is used to clear a file.

Options

FileName

The name of the file to be cleared.

Example

```
m_FileClrData ${DATA}/PJ01DDD.BT.QSAM.KBSTO045
```

m_FileDelete

Name

`m_FileDelete` — Deletes a file.

Synopsis

```
m_FileDelete FileName
```

Description

`m_FileDelete` is used to delete a file.

Options

FileName

The name of the file to be deleted.

Example

```
m_FileDelete ${DATA}/PJ01DDD.BT.QSAM.KBSTO045
```

m_FileEmpty

Name

m_FileEmpty – Checks whether a file is empty.

Synopsis

```
m_FileEmpty -r ReturnVariable FileName
```

Description

m_FileEmpty is used to check whether a file is empty.

Options

-r ReturnVariable

Returns “true” or “false”.

FileName

The name of the file to be checked.

Example

```
m_FileEmpty -r MY_VARIABLE ${DATA}/rextest2
if [[ ${MY_VARIABLE} = true ]]; then
    echo "file is empty"
else
    echo "file is not empty"
fi
```

m_FileExist

Name

m_FileExist – Checks the presence of a file.

Synopsis

```
m_FileExist -r ReturnVariable FileName
```

Description

m_FileExist is used to check whether a file is present.

Options

-r ReturnVariable

Returns “true” or “false”.

FileName

The name of the file to be checked.

Example

```
m_fileExist -r MY_VARIABLE ${DATA}/rextest2
if [[ ${MY_VARIABLE} = true ]]; then
    echo "file exists"
else
    echo "file does not exist"
fi
```

m_FileLoad

Name

m_FileLoad — Loads a file.

Synopsis

```
m_FileLoad [-C] [-S] Infile [Infile ...] Outfile
```

Description

This function loads a file.

Options

-C

Number of records to copy from the `Infile` to the `Outfile`.

-S

Number of records to skip when copying from the `Infile` to the `Outfile`.

Example

```
m_FileLoad ${DD_SYSUT1} ${DD_SYSUT2}
```

m_FileOverride

Name

m_FileOverride — Overrides a file.

Synopsis

```
m_FileOverride -i [-D Delimiter] -g [CUR|ALL [--+np][rang]] -s label ddname  
m_FileOverride -d [-r RecSize -t Type [-k key]] -g [CUR|ALL [--+np][rang]]  
-s label ddname dsname
```

Description

m_FileOverride overrides a file assignment, this assign has priority over a standard assign ([m_FileAssign](#)).

Options

Only “-s” and one of the two options “-i” and “-d” are mandatory to specify the usage. All other options are optional. See [m_FileAssign](#) for other options.

-s <label>

Name of the label in the called procedure.

Example

```
m_FileOverride -i -s PR3STEP1 SYSIN  
  
m_FileOverride -d OLD -s MYSORT CUSTOM  
${DATA}/BEAUSR2.QSAM.CUSTOM
```


m_FilePrint

Name

m_FilePrint — Prints a file (IDCAMS command PRINT).

Synopsis

```
m_FilePrint {-i ddname|-I dsname} {-o ddname|-O dsname}[-t][-C] [-S]
```

Description

This function prints a file.

Options

-C

Optional: Number of records to be listed.

-S

Optional: Number of records to skip before the listing begins.

-i infile|-I indataset

The input file is either a ddname (infile) or a dsname (indataset).

-o ddname|-O dsname

Optional: The output file is either a ddname (outfile) or a dsname (outdataset) (default value: SYSPRINT)

-t {CHAR|DUMP|HEX}

Optional: Type of print (default value: DUMP).

CHAR: specifies each byte of a record is to be listed as character.

DUMP: specifies each byte of a record is to be printed in both hexadecimal and character format.

HEX: specifies each byte of a record is to be listed as hexadecimal digits.

Example

```
m_FilePrint -I ${DATA}/INPUT -C 1
```

```
m_FilePrint -i INPUT -t CHAR -C 5
```

m_FileRepro

Name

m_FileRepro — Copies a file (IDCAMS command REPRO).

Synopsis

```
m_FileRepro {-i ddname|-I dsname} {-o ddname|-O dsname} [-C] [-S]
```

Description

This function copies a file.

Options

-C

Optional: Number of records to be copied.

-S

Optional: Number of records to skip before the copy begins.

-i infile|-I indataset

The input file is either a ddname (infile) or a dsname (indataset).

-o ddname|-O dsname

Optional: The output file is either a ddname (outfile) or a dsname (outdataset) (default value: SYSPRINT)

Example

```
m_FileRepro -I ${DATA}/INPUT -C 1
```

```
m_FileRepro -i INPUT -C 5
```

m_FileSort

Name

m_FileSort — Sorts a file.

Synopsis

```
m_FileSort -s SortSpecificationFile -i Infile [Infile ...] -o [Outfile]
```

Description

This function sorts a file.

Options

-s SortSpecification File

The sort specification indicates either a file containing the sort specification or a file that indicates where the sort specification is to be found (ddname of file, by default SYSIN).

-i Infile

At least one file must be used as input to the sort (ddname of file, by default SORTIN).

-o Outfile

File to be used as output to the sort (ddname of file, by default SORTOUT).

Example with SyncSort commands

```
m_FileAssign -i TOOLIN
/FIELDS FLD1 5 CH 5
/COND ...
/OMIT ...
_end
m_FileSort -s TOOLIN -i SORTIN -o SORTOUT
```

m_FileRename

Name

m_FileRename – Renames a file.

Synopsis

```
m_FileRename OldName NewName
```

Description

m_FileRename is used to rename a file.

Options

NewName

The new name of the file.

OldName

The old name of the file.

m_Ftp

Name

m_Ftp — Executes an FTP process.

Synopsis

```
m_Ftp -i <inputfile> [-e <ExitReturnCode>] [-n NETRC]
```

Description

This function reproduce the z/OS feature :EXEC PGM=FTP.

This function launches an ftp process and executes ftp command(s) stored in an input file.

An environment variable MT_FTP_TEST must be declared and initialized with the following value (upper or lower case):

Y or YES : test mode. The ftp commands different from “open”, “user”, “quit” or “bye” will not be executed.

N or NO: real mode. All the ftp commands will be executed.

Options

-i <inputfile>

Mandatory parameter.

ddname of the file which contains the ftp commands.

-e <ExitReturnCode>

Optional parameter.

Numeric return code to be returned when an error occurred during ftp execution.

If ExitReturnCode = nn, the return code will be “C00nn” in case of ftp error.

If the parameter does not exist, the return code is always C0000.

-n NETRC

Optional parameter.

Necessary when the ftp connection is executed through “.netrc” file.

So “user” and “password” are omitted in <inputfile>.

Examples

```
m_FileAssign -d ANY MT_LOC01 ${DATA}/ftp_file_loc1
m_FileAssign -i SYSIN
open host
user user1 pw1
put MT_LOC01 DIR/file2
quit
_end
m_Ftp -i INPUT
```

Notes

Some notes concerning the lines in the “SYSIN” file.

- The first line must be “open”:

format: open <HOSTNAME or ADDRESS>

example: open 172.20.12.21

- The second line must set the user ID and the password if the “-n NETRC” parameter is not set.

format: user <user> <password>

When the “-n NETRC” parameter is present, it implies that a “.netrc” file exist. This file identifies the user ID and the password to be used.

- The following lines are ftp’s commands (one per line) as get, put, ...

- The last line must be “quit”:

format: quit

m_GenCommit

Name

`m_GenCommit` — Commits a generation file.

Synopsis

```
m_GenCommit [GDG base name]
```

Description

`m_GenCommit` commits a generation file. During the job execution, all created generations stay temporarily until the end of the job in which these generations are committed. This function permits an explicit commit of temporary generations before the job ends.

Options

`GDG base name`

 Name of the generation file to commit.

m_GenDefine

Name

`m_GenDefine` — Defines a GDG base name.

Synopsis

```
m_GenDefine -s --nb_occurs <GDG base name>
```

Description

This function defines the generation file and generates a file ".gens" which contains the number of generations that should be kept (specified by option "-s").

Options

-s

Number of occurrences of generation file to keep on disk.

GDG base name

The name of the `GDG base` for which the maximum number of generations is being defined.

Example

```
m_GenDefine -s 31 ${DATA}/PJ01DDD.BT.GDG.KBIDU001
```


m_GenRollback

Name

m_GenRollback — Rolls back a generation GDG base name.

Synopsis

```
m_GenRollback [GDG base name]
```

Description

This function rolls back a GDG base name. During the job execution, all created generations stay temporarily until the end of the job in which these generations are committed. This function permits an explicit rollback of temporary generations before the job ends.

Options

GDG base name

Name of the generation file to rollback.

m_JclLibSet

Name

m_JclLibSet — Specify conversion stage Procedure and Include directories.

Synopsis

```
m_JclLibSet directory
```

Description

m_JclLibSet specifies the directories where Procedures and Includes are stored during the conversion phase.

Options

directory

Path and name of the directory.

Example

```
m_JclLibSet PJ01DDD.BT.INCLUDE.SRC
```

m_JobBegin

Name

m_JobBegin — Used to begin a job.

Synopsis

```
m_JobBegin -j jobname [-C cond] [-c class] [-p priority] [-r restart] [-t
typrun] -v version -s start_label
```

Description

Indicates the parameters that are used on the z/OS job card with the JES2 interface. The parameters are stored in the following files:

- *class* is stored in the *JOBID.class* file
- *restart* is stored in the *JOBID.restart* file
- *priority* is stored in the *JOBID.priority* file
- *typrun* is stored in the *JOBID.typrun* file

Options

-j *jobname*

The name of the job to launch.

-C *condition*

Specifies the return code tests used to determine whether a job will continue processing or be terminated.

-c *class*

The execution class of the job.

-p *priority*

The execution priority of the job.

-r *restart*

The name of the step to use to restart the job.

-t *typrun*

Indicates what should be done with the job. One of the following choices:

COPY – Copy the job directly in an output stream to sysout.

Oracle Tuxedo Application Runtime for Batch Functions

`HOLD` – The system should hold the job.

`JCLHOLD` – JES2 should hold the job.

`SCAN` – Scan JCL for syntax errors only.

`-v version`

version of the ksh script.

`-s start_label`

Start label — label of the first phase to be started.

Example

```
m_JobBegin -j PJ01DSTA -s START -v 1.0 -t SCAN
```

m_JobEnd

Name

m_JobEnd — Ends a job.

Synopsis

m_JobEnd

Description

This function is used to end a job.

Options

None

m_JobLibSet

Name

m_JobLibSet — Specifies where programs are stored.

Synopsis

```
m_JobLibSet directory [:directory[:directory...]]
```

Description

This function specifies at job level the directory in which programs are stored.

Options

directory [:directory[:directory...]]

Path and name of the directory containing executable programs.

m_OutputAssign

Name

m_OutputAssign – manages DD SYSOUT statements with the following parameters: CLASS, COPIES, DEST, FORMS and HOLD.

Synopsis

```
m_OutputAssign [-c][-w][-n][-d][-f][-H][-o][-D] ddname
```

Options

-c <class>

Class of the output queue.

-w <writer>

- INTRDR:

At the end of the m_ProgramExec function, submits the contents to TuxJes (hopefully a script shell).

- SMTP:

At the end of the m_ProgramExec function, submits the contents (hopefully SMTP commands) to send an email using the SMTP protocol.

-<writer>:

At the end of the m_ProgramExec function, submits the command associated with the <writer> name in the writer.conf file.

-n <copies>

Number of copies to print.

-d <dest>

Destination of the printing.

-f <forms>

Name of the used form

-H<Y/N>

Specifies whether the print must held or not.

N is the default value.

-o <reference[,reference,...]>

List of " OUTPUT " references.

-D <dsname>

Data set name.

ddname

Data Definition Name

Examples

Example with an output class A:

```
m_OutputAssign -c A SYSOUT
```

Example with INTRDR:

In this case, the file which ddname is RDRICICO must contain a ksh script.

```
m_OutputAssign -c R -w INTRDR RDRICICO
```

Example with an "output" reference:

The output EDI is referenced.

```
m_OutputAssign -c A -o "*.EDI" SYSPRINT
```


m_OutputOverride

Name

m_OutputOverride – Overrides an output file.

Synopsis

```
m_OutputOverride [-c class][-n copies][-d dest][-f forms][-H][-o list of  
output][-D dsname] -S Labelproc ddname
```

Description

This function overrides a sysout assignment (see [m_OutputAssign](#)).

Options

Only “-S” is mandatory, which specifies the step where the assignment is overridden. All other options are optional. See [m_OutputAssign](#) for other options.

-S <label>

Name of the label in the called procedure.

m_OutputSet

Name

m_OutputSet — manages the "OUTPUT JCL" statement with the following parameters: CLASS, COPIES, DEFAULT, DEST, FORMS, PRIORITY and WRITER.

It defines a reference and specifies associated processing options for sysout management.

Synopsis

```
m_OutputSet [-c][-n][-d][-f][-p][-w][-D] Reference
```

Options

-c <class>

Class of the output queue.

-n <copies>

Number of copies to print.

-d <dest>

Destination of the printing.

-f <forms>

Name of the form used.

-p <priority>

Specifies the priority of the output.

-w <external writer>

Specifies the use of an “external writer” to process the sysout file rather than TuxJes.

-D Y/N

Default reference (Y/N).

Y indicates that the reference can be implicitly referenced in following m_OutputAssign function calls.

N indicates that the reference can not be implicitly referenced in following m_OutputAssign function calls.

Reference

Reference name of the output. This name (and its associated characteristics) can be referenced in following m_OutputAssign function calls.

Example

```
m_OutputSet -d LOCAL -D N EDI  
m_OutputAssign -c L -o "*.EDI" SYSUT2
```

m_PhaseBegin

Name

m_PhaseBegin — Called at the beginning of a script phase.

Synopsis

m_PhaseBegin

Description

This function is called at the beginning of a script phase.

Options

None.

m_PhaseEnd

Name

m_PhaseEnd — Called at the end of a script phase.

Synopsis

m_PhaseEnd

Description

This function is called at the end of a script phase.

Options

None.

m_Pkzip

Name

m_Pkzip — Executes zip process.

Synopsis

```
m_Pkzip [-f][-F] -a [-k][-n][-g][-d]
```

Description

This function zips files, directories or members of directory in an archive.

Messages are reported in SYSPRINT file.

Note: the options “-f” and “-F” are not mandatory but at least one must be present.

Options

-f ‘<ddname1>[,<ddname2>[,<ddname3>]...]’
First format of “-f” option, optional.

ddname of the files to be zipped (enclosed with a single quote).

Multiples ddname must be separated by a comma (,).

-f ‘<dirname>[;<member1>...]’
Second format of “-f” option, optional.

dirname followed by member names to be zipped (enclosed with a single quote).

Member names must be separated by a semicolon (;).

When dirname is alone, all the members are zipped.

Wildcard (*or %) may be used (for member names only).

-F ‘<dsname1>[,<dsname2>[,<dsname3>]...]’
Optional.

dsname of the files to be zipped (enclosed with a single quote).

Multiples dsname must be separated by a comma (,).

-a <archive>

mandatory.

ddname of the archive in which zipped file(s) are stored.

-k <action>

Optional.

Action to be done (ADD by default).

Use UPDATE to overwrite in archive.

-n '<zipped_name>'

Optional.

Names of the zipped file(s) in the archive (enclosed with single quotes) separated by a comma (,).

When several files are zipped, the same order than done in option “-f” followed by option “-F” must be respected.

-g <Y|N>

Optional.

GZIP compatible format.

Reserved for future used. This option is not taken into account by the RunTime Batch.

-d '<zipdir>'

Optional.

Directory (enclosed by single quotes) where files(s) to zip are located (\${DATA} by default).

Examples

In the following example, 2 files are to be zipped (ddname's FICIN01 and FIC02) named by the “-f” option, DDARCH (ddname of the archive) is named by the “-a” option while the first file will be renamed (see the “-n” option).

```
m_FileAssign -d SHR FICIN01 ${DATA}/PKZIP_FICIN01
m_FileAssign -d SHR FIC02 ${DATA}/FIC.FILE01
m_FileAssign -d NEW,CATLG DDARCH ${DATA}/ARCH.FILE
m_Pkzip -f 'FICIN01,FIC02' -a DDARCH -n 'NEW_FICIN01,'
```

Oracle Tuxedo Application Runtime for Batch Functions

The following example shows how to use at the same time the options “-f” “-F” and “-n”.

```
-f `ddn1,ddn2,ddn3,pds;member1;member2`  
-F `dsn1,dsn2,dsn3`  
-n ` ,newddn2,newddn3,newmb1 , ,newdsn1,newdsn2,`
```

The ddn1, member2 and dsn3 are not renamed (they are replaced by comma(,)).

m_Pkunzip

Name

m_Pkunzip — Executes unzip process.

Synopsis

```
m_Pkunzip [-f][-F] -a [-k][-n][-g][-d][-o][-w]
```

Description

This function unzips files, directories or members of directory in an archive.

Messages are reported in SYSPRINT file.

Note: the options “-f” and “-F” are not mandatory but at least one must be present.

Options

-f ‘<ddname1>[,<ddname2>[,<ddname3>]...]’

Optional.

ddname of the outfile(s) to be unzipped (enclosed with a single quote).

Multiples ddname must be separated by a comma (,).

-F ‘<dsname1>[,<dsname2>[,<dsname3>]...]’

Optional.

dsname of the outfile(s) to be unzipped (enclosed with a single quote).

Multiples dsname must be separated by a comma (,).

-a <archive>

Mandatory.

ddname of the archive from which zipped file(s) are extracted.

-o <outddname>

Optional.

ddname of the outfile into which file(s) are to be extracted.

-k <action>

Optional.

Action to be done (EXTRACT by default).

Note: only EXTRACT is supported in this release.

-n '<zipped_name>'

Optional.

Names of the zipped file(s) in the archive (enclosed with single quotes) separated by a comma (,).

When several files are zipped, the same order than done in option “-f” followed by option “-F” must be respected.

-g <Y|N>

Optional.

GZUNZIP compatible format.

Reserved for future used. This option is not taken into account by the RunTime Batch.

-w <Y|N>

Optional.

Overwrite parameter (default N).Used to overwrite an existing file.

-d '<unzipdir>'

Optional.

Directory (enclosed by single quotes) where files(s) to unzip are to be stored ({DATA} by default).

Examples

Unzip all files of an archive without renaming files:

```
m_FileAssign -d NEW,CATLG DDARCHIV ${DATA}/PKZIP_ARCH  
m_Pkunzip -a DDARCHIV
```

Unzip all files of an archive into an output file:

```
m_FileAssign -d NEW,CATLG DDARCHIV ${DATA}/PKZIP_ARCH  
m_FileAssign -d NEW,CATLG OUTFILE ${DATA}/UNZIPPED.FILE  
m_Pkunzip -a DDARCHIV -o OUTFILE
```


m_ProcBegin

Name

m_ProcBegin — Begins an in-stream procedure.

Synopsis

```
m_ProcBegin ProcedureName
```

Description

An in-stream procedure is added at the end of a korn shell script (by Oracle Tuxedo Application Runtime WorkBench during the translation) and referenced by m_ProcInclude.

Options

ProcedureName

Name of the procedure to include.

Example

```
m_ProcBegin KBPRB007
```

m_ProcEnd

Name

m_ProcEnd — Ends an in-stream procedure.

Synopsis

m_ProcEnd

Description

An in-stream procedure added at the end of a korn shell script is ended by m_ProcEnd.

Options

None.

m_ProcInclude

Name

m_ProcInclude — Calls a procedure to be included in the script during the conversion phase.

Synopsis

```
m_ProcInclude ProcedureName [param1=value1,param2=value2,...,paramN=valueN]
```

Description

Options

ProcedureName

Name of the (in-stream or catalogued) procedure to include.

Example

```
m_ProcInclude BPRAF001
```

m_ProgramExec

Name

m_ProgramExec — Executes a program.

Synopsis

```
m_ProgramExec [-b] [-e exit_type:exit_name] Program [arguments]
```

Description

This function runs a COBOL program.

Options

-b

Indicates the database will be accessed by the program.

-e exit_type:exit_name

Indicates an exit routine should be used.

An exit routine may be used at the beginning and/or at the end of a program.

The exit type (BEGIN, END or BOTH) indicates if the exit routine must be called at the begin or at the end of the program (or both).

The exit name is used to build the names of the sub-programs to be inserted before the call to the program (RTEX-"exitName"-Begin) and after the call of the program (RTEX-"exitName"-End).

Program [arguments]

Program name and user arguments to be passed to the program.

Examples

```
m_ProgramExec BPRAB006 "08"
```

Indicates to run program BPRA006 with the parameter "08"

```
m_ProgramExec -b BDBAB001
```

Indicates that the program BDBAB001 accesses the Data Base

Note: To pass a parameter to a program

The <"> (double quote) character is used to mark out the boundaries of the parameters

Examples:

Oracle Tuxedo Application Runtime for Batch Functions

PARM=MT5 on z/OS becomes "MT5" on target

PARM=(MT5,MT6) on z/OS becomes "MT5,MT6" on target

PARM='S=MT5' on z/OS becomes "S=MT5" on target

PARM=('S=MT5','Q=MT6') on z/OS becomes "S=MT5,Q=MT6" on target

Two successive <"> (2 simple quotes) are replaced on one <'> (1 simple quote).

PARM='5 O' 'CLOCK' becomes "5 O' CLOCK"

Two successive <&&> (2 ampersands) are replaced by one <&> (1 ampersand) character.

'&&TEMP' becomes "&TEMP"

```
m_ProgramExec -e BEGIN:EX1 BPRAB006
```

Indicates to run program BPRAB006 after the call of the “exit routine” RTEX-EX1-Begin.

This “exit routine” written by the user may contain user actions (for example concerning “accounting”).

m_RcSet

m_RcSet <ARGS> ReturnCode [Message]

Name

m_RcSet — Sets the return code.

Synopsis

```
m_RcSet ReturnCode [Message]
```

Description

m_RcTest sets the return code of a function.

Options

ReturnCode

The value of the return code of the current phase.

Message

A message that may be displayed with the return code.

Examples

```
m_RcSet ${MT_RC_ABORT:-S999} "Unknown label : ${CURRENT_LABEL}"
```

```
m_RcSet 0
```

m_SendMail

Name

m_SendMail — Sends an email.

Synopsis

```
m_SendMail -t [-f] [-s] [-m] [-a] [-n] [-c] [-b]
```

Description

This function sends an e-mail.

When the option “-f” is omitted, the environment variable MT_FROM_ADDRESS_MAIL must be declared in the user’s profile and initialized with the “From Adress” to be used by default.

Two environment variables are used (see RTBatch.conf file):

MT_SMTP_SERVER : SmtptServer (default value : “localhost”)

MT_SMTP_PORT: SmtptPort (default value : “25”)

Options

-t ‘<To-Address1>[,<To-Address2>...]’

Mandatory option. At least, one “To-Address” must be declared.

Electronic mail address of the recipient(s) inclosed in single quotes.

Multiple addresses must be separated by a comma “,”.

-f ‘<To-Address>’

Optional.

Electronic mail address of the sender inclosed in single quotes.

The environment variable MT_FROM_ADDRESS_MAIL is used when this option is missing.

-s “<Subject>”

Optional.

Subject of the email inclosed in double quotes.

-m <message file>

Optional.

ddname of the file containing the message of the email.

-a <attach-file1>[,<attach-file2>...]

Optional.

ddname of the attached document(s).

Multiple attachments must be separated by a comma “,”.

-n <filename1>[,<filename2>...]

Optional.

Name of the attached document(s) referenced by option “-a”.

Multiple names must be separated by a comma “,”.

Note that there must have so many name as ddname.

-c <cc-Address1>[,<cc-Address2>...]

Optional.

Electronic mail address of the Copy Carbon recipient(s) included in single quotes.

Multiple addresses must be separated by a comma “,”.

-b <bcc-Address1>[,<bcc-Address2>...]

Optional.

Electronic mail address of the Blind Copy Carbon recipient(s) included in single quotes.

Multiple addresses must be separated by a comma “,”.

Example

In this example,

- the text of the message is stored in the sysin MESSAGE,
- the implicit “From-Address” is taken into the environment variable MT_FROM_ADDRESS_MAIL,
- the “To-Address” is ”BOB” <BOB.FOSTER@USA.COM>,
- an attached document is to be sent (with ddname file CR1 and name FILE2.CSV).

Oracle Tuxedo Application Runtime for Batch Functions

```
m_FileAssign -i MESSAGE
```

```
text of the email
```

```
_end
```

```
m_FileAssign -d SHR CR1 ${DATA}/FPROD.FILE1
```

```
m_SendMail -t ""BOB" <BOB.FOSTER@USA.COM>' -m MESSAGE -a CR1 -n 'FILE1.CSV'
```

m_ShellInclude

Name

m_ShellInclude — Inserts a part of script.

Synopsis

```
m_ShellInclude script name
```

Description

This function inserts a part of script.

Options

script name

Name of the part of a script to be included in the script shell during the conversion phase.

m_Smtp

Name

`m_Smtp` — Sends an email using SMTP protocol.

Synopsis

`m_Smtp -i`

Description

This function sends an e-mail using SMTP protocol.

The SMTP commands are stored in the input file.

The command uses the following format:

```
telnet <SmtpServer> <SmtpPort>
```

Two environment variables are used:

`MT_SMTP_SERVER` : SmtpServer (default value : “localhost”)

`MT_SMTP_PORT`: SmtpPort (default value : “25”)

Options

-i <InputFile>

Mandatory option.

ddname of the file containing the SMTP commands.

Example

```
m_Smtp -i SYSUT2
```

m_StepLibSet

Name

m_StepLibSet — Specifies where programs are stored.

Synopsis

```
m_StepLibSet directory [:directory[:directory...]]
```

Description

m_StepLibSet specifies at step level where programs are stored. This information is interpreted when the program is to be executed.

Options

directory

Path and name of the directory containing executable programs.

m_SymbolDefault

Name

`m_SymbolDefault` — Assigns a value to a symbol.

Synopsis

```
m_SymbolDefault var=value
```

Description

Used before the call of a procedure to define default substitution texts for symbols in the procedure.

This function will be analyzed and taken into account during the conversion phase and the symbols replaced by their value in the extended script.

Options

var

Name of the variable.

Value

Value assigned to the variable.

Example

```
m_SymbolDefault VAR=45
```


m_SymbolSet

Name

m_SymbolSet — Defines a symbol.

Synopsis

```
m_SymbolSet var=value
```

Description

Defines a symbol and assigns a value before the first use of this symbol.

Options

var

Name of the variable.

Value

Value assigned to the variable.

Example

```
m_SymbolSet VAR=45
```

m_UTILITYExec

Name

m_UTILITYExec — Executes the stored commands.

Synopsis

```
m_UTILITYExec [sysin file]
```

Description

Executes the contents of an external sysin. This function executes the script “UTILITYName” in the current Shell. UTILITYName is the physical name previously assigned to [sysin file].

The script assigned with sysin should contain a sequence of RunTime Batch functions. Although this function can also launch native Korn shell scripts, it is recommended to use m_PROGRAMExec instead. In this way, assignation is not required.

Options

sysin file:

By default SYSIN.

ddname of a sysin file which contains function to launch.

Example

```
m_FileAssign -d NEW SYTSIN ${SYSIN}/SYSTIN/MUEX07.sysin  
m_UTILITYExec SYTSIN
```

The file MUEX07.sysin may have the following content:

```
m_PROGRAMExec -b ZVDL101
```

Tuxedo Job Enqueueing Service (TuxJES)

This chapter describes servers, commands and utilities included in the TuxJES feature.

[Table 1](#) lists TuxJES commands and functions.

Table 1 TuxJES Servers, Commands and Utilities

Name	Description
genjesprofile	Generates the security profile for TuxJES system
artjesadmin	TuxJES command interface.
ARTJESADM	TuxJES administration server.
ARTJESCONV	TuxJES conversion server.
ARTJESINITIATOR	TuxJES job control API.
ARTJESPURGE	Purges job queue.
TuxJES Queue System	TuxJES Queue system.
TuxJES User Substitution	Defines the specific OS user to execute jobs

genjesprofile

Name

`genjesprofile` – Generates the security profile for TuxJES system

Synopsis

```
genjesprofile [-f userprofile]
```

Description

This utility generates the security profile for TuxJES system. When `genjesprofile` is launched, you are prompted to enter the Oracle Tuxedo application password, user name, user password and the database connection (`MT_DB_LOGIN`). The output is a security profile file which contains the Oracle Tuxedo application password, user name, user password and the database connection with the file permission “-rw-----”.

Note: The generated security profile file can be used by the [artjesadmin](#) tool to login to an Oracle Tuxedo domain.

Parameters and Options

`genjesprofile` supports the following parameters and options:

`[-f <output_file>]`

The location of the generated security profile file. If this option is not specified, the default value is `~/ .tuxAppProfile`.

See Also

[artjesadmin](#)

artjesadmin

Name

`artjesadmin` – TuxJES command interface.

Synopsis

```
artjesadmin [-f [security_profile]]
```

Description

`artjesadmin` is the TuxJES command interface. It requires the TuxJES system must be started first.

Parameters and Options

`artjesadmin` supports the following parameters and options:

-f

The security profile file generated by `genjesprofile`. The default value is `~/ .tuxAppProfile`. It requires the owner of the security profile must be the user who runs `artjesadmin`. The user name in this profile is the owner of the submitted jobs. A job without a specified owner is assigned the owner name "*".

A job with a particular owner can only be controlled by that owner. A job without a particular owner (*) can be controlled by anyone. Any user can print all jobs.

`artjesadmin` supports the following sub commands:

submitjob(smj) [-o='xxx'] -i scriptfile

Submits a job to TuxJES system. The `scriptfile` parameter is the job script to be submitted.

Note: `artjesadmin` is not responsible for scriptfile propagation. It must be located on a shared file system if the conversion and execution are not on same machines. The options are as follows:

`-o='xxx'`: Specifies the options passed to the EJR script file using the `-i` option.

`-i =scriptfile`: The script file.

Once successfully invoked, the return format `Job xxx` is submitted successfully. If an error occurs, an error message is printed.

`artjesadmin` also supports direct job submission using the following format:

```
artjesadmin [-o='xxx'] -i scriptfile
```

`artjesadmin` has a return code different from zero if there is an error occurs as listed in [Table 2](#)

Table 2 Error Codes

Code	Description
0	No runtime error
251	artjesadmin it self command error returned by ARTJESADM server
252	JES2SUBMIT service error
Others	EJR none zero exit code

`printjob(ptj) -n jobname | -j jobid | -c job_class [-a [-v]]`
 Displays the existing jobs. If no option is specified, it displays all jobs. The options are as follows:

- n jobname: Display jobs with given job name
- j jobid: Display a particular job information
- c job_class: Display a particular class jobs information
- a: Display all jobs
- v: Verbose mode

Listing 1 printjob Output

```
> ptj -a
JOBNAME JobID      Owner      Prty C      Status
-----
cjob     00000015 *           5 A      DONE
cjob     00000016 *           5 A      DONE
cjob     00000018 *           5 A      CONVING

total:3
success:3
```

- JOBNAME: The job name.
- JobID: The job ID generated by TuxJES system

- Owner: Job Owner.
- Prty: Job priority
- c: The job class.
- Status: Job status
 - EXECUTING: a job is running
 - CONVING: a job waiting for conversion
 - WAITING: a job waiting for execution.
 - DONE: a job finished successfully.
 - FAIL: a job finished but failed
 - HOLD_WAITING: a JOB is in hold state after conversion
 - HOLD_CONVING: a job is in hold state without conversion
 - INDOUBT: a job is in doubt state due to its initiator restarted

In verbose mode, the job detail information is displayed:

- Submit time: The submit time of the job
- Step: The current running job step. It is only applicable to running jobs.
- Type Run: The TYPRUN definition of the job.
- Machine: Only for running/done/failed jobs. It is the machine name that the job is/was running on.
- CPU usage: The user CPU usage and system CPU usage for the job execution.
- Result: Job operation result, "OK" or error message.

If no option is specified, the "-a" option is assumed.

holdjob(hj) -n job name | -j jobid | -c job_class | -a
 Hold the specified jobs which are in CONVING or WAITING status. The options are as follows:

- n jobname: Hold jobs with given job name
- j jobid: Hold a particular job
- c job_class: Hold a particular class jobs
- a: Hold all jobs

If no option is specified, the "-a" option is assumed.

releasejob(rlj) -n job name | -j jobid | -c job_class | -a

Releases the jobs in HOLD_WAITING or HOLD_CONVERTING status so that they can be picked up by ARTJESCONV for conversion or ARTJESINITIATOR for running. The options are as follows:

- n jobname: Release jobs with given job name
- j jobid: Release a particular job
- c job_class: Release a particular class jobs
- a: Release all jobs

If no option is specified, the "-a" option is assumed.

canceljob(cj) -n job name | -j jobid | -c job_class | -a

Cancels a job and moves it to the output queue. For running jobs, this command informs the related ARTJESINITIATOR to invoke EJR with "-k" option. Other jobs are moved directly to the output queue. The TuxJES system assumes the job is terminated when EJR returns. The options are as follows:

- n jobname: Cancel jobs with given job name
- j jobid: Cancel a particular job
- c job_class: Cancel a particular class jobs
- a: Cancel all jobs

If no option is specified, the "-a" option is assumed.

purgejob(pgj) -n job name | -j jobid | -a

Completed jobs in the output queue are moved to the purge queue. For other jobs, `purgejob` has same effect as `canceljob`. The `purgejob` command does not purge the job directly. The ARTJESPURGE server deletes the job from the TuxJES system. If ARTJESPURGE is not started, the job remains in the output queue.

The options are as follows:

- n jobname: Purge jobs with given job name
- j jobid: Purge a particular job
- a: Purge all jobs

If no option is specified, the "-a" option is assumed.

changeconcurrent(chco) -g groupname -i serverid -n concurrent_num

Changes the number of maximum concurrent executing jobs for the ARTJESINITIATOR server which is designated by the -g and -i options. The change takes effect with no need to restart the ARTJESINITIATOR server.

The options are as follows:

- g groupname: the Tuxedo group name of the ARTJESINITIATOR server
- i serverid: the Tuxedo server id of the ARTJESINITIATOR server
- n concurrent_num: the number of maximum concurrent executing jobs

The change is not persistent, which means the number is reset when the ARTJESINITIATOR server restarts.

printconcurrent(pco) -g groupname -i serverid

Displays the number of maximum concurrent executing jobs for the ARTJESINITIATOR server which is designated by -g and -i options.

The options are as follows:

- g groupname: the Tuxedo group name of the ARTJESINITIATOR server
- i serverid: the Tuxedo server id of the ARTJESINITIATOR server

event (et) [-t S,C,E,P,A] on|off

This command tells artjesadmin to subscribe particular job event. The options are:

- S: job submission event; the event name is ARTJES_JOBSSUBMIT
- C: job conversion complete event; the event name is ARTJES_JOBCVT
- E: job execution finish event; the event name is ARTJES_JOBEXEC
- P: job purge event; the event name is ARTJES_ARTJESPURGE
- A: all supported events. If the event is set to "on", A is the default.

on |off: The submission is on or off. the "on" setting can be used with the -t option. "off" will unsubscribe all event subscriptions.

If the subscribed event type is not configured in JESCONFIG, an error is reported.

verbose(v) on|off

Turn on /off verbose mode.

See Also

[Oracle Tuxedo Application Runtime for Batch User Guide](#)

ARTJESADM

Name

ARTJESADM – TuxJES Administration server.

Synopsis

```
ARTJESADM
SRVGRP="identifier"
SRVID="number" CLOPT=" [-A][servopts options] -- -i JESCONFIG"
```

Description

ARTJESADM is an Oracle Tuxedo application server provided by TuxJES. The `artjesadmin` command communicates with ARTJESADM for most tasks.

ARTJESADM must be configured in the `UBBCONFIG` file in front of other TuxJES servers since others they access services provided by ARTJESADM. If `JESCONFIG` is changed, all TuxJES related servers must be restarted for new configurations to take effect.

Parameters and Options

ARTJESADM supports the following parameters and options:

-i JESCONFIG

`JESCONFIG` represents the full path name of the TuxJES system configuration file. It allows the following parameters:

`JESROOT`

The full path name of the root directory to store job information. It is a mandatory attribute. If this directory does not exist, ARTJESADM creates it automatically.

`JESROOT=/xxx/xxx`

`DEFAULTJOBCLASS`

The default job class if the job class is not set for a job. It is an optional attribute. The default job class is `A` if this attribute is not set.

`DEFAULTJOBCLASS=[A-Z], [0=9]`

`DEFAULTJOBPRIORITY`

The default job priority if the job priority is not set for a job. It is an optional attribute. The default job priority is `0` if this attribute is not set.

`DEFAULTJOBPRIORITY=[0-15]`

DUPL_JOB=NODELAY

If it is not set, only one job can be in execution status for a job name. NODELAY will remove the dependency check. The default value is delay execution.

EVENTPOST=S, C, E, P, A

Specifies whether events are posted for a job at particular stages.

S: Job submission event. Event name: ARTJES_JOBSSUBMIT

C: Job conversion complete event. Event name: ARTJES_JOBSCVT

E: Job execution finish event. Event name: ARTJES_JOBFINISH

P: Job purge event. Event name:ARTJES_JOBPURGE

A: All supported events.

If EVENTPOST is not specified, no events are posted. The data buffer with event pos is FML32 type and the fields are defined in JESDIR/include/jesflds.h.

JOBREPOSITORY

The path of the job repository where jobs are stored. The script file path inputted in job submitting may be a relative path in JOBREPOSITORY if it is set.

PRIVILEGE_MODE

Specifies whether and how to enable the user substitution (See [TuxJES User Substitution](#)). The values are:

NONE: Default value. Indicates jobs are executed by the OS user who starts JES system. This is compatible with all previous implementations on JES system.

USER_IDENTICAL: Indicates jobs are executed by the Oracle Tuxedo user with which JES client joins JES system. Make sure that each Oracle Tuxedo user corresponds to an existing OS user before you choose this value.

USER_MAPPING: When this value is specified, the JES system looks up the TuxJES user mapping file and finds out the OS user corresponding to the Oracle Tuxedo user with which JES client joins JES system, and then appoints this OS user as the job executor.

USER_MAPPING_FILE

The full path where TuxJES user mapping file is stored. It is used along with PRIVILEGE_MODE when its value is USER_MAPPING.

It is recommended that the owner of user mapping file is root and the file permission is "-rw-----".

One Oracle Tuxedo user must be mapped to one OS user only, and it is recommended that one OS user is mapped to one Tuxedo user as well.

Tuxedo Job Enqueueing Service (TuxJES)

Example(s)

UBBCONFIG example:

```
ARTJESADM
```

```
SRVID=1 SRVGRP=SYSGRP CLOPT="-A -- -i /nfs/users/jes/jesconfig"
```

See Also

[Oracle Tuxedo Application Runtime for Batch User Guide](#)

ARTJESCONV

Name

ARTJESCONV – TuxJES conversion server.

Synopsis

```
ARTJESCONV
```

```
SRVGRP="identifier"
```

```
SRVID="number" CLOPT=" [-A][servopts options] -- "
```

Description

The TuxJES conversion server. It is responsible for invoking the EJRC to do the job conversion.

Example(s)

UBBCONFIG example:

```
ARTJESCONV
```

```
SRVID=2 SRVGRP=SYSGRP CLOPT="-A -- "
```

See Also

[Oracle Tuxedo Application Runtime for Batch User Guide](#)

ARTJESINITIATOR

Name

ARTJESINITIATOR – Job Initiator

Synopsis

```
ARTJESINITIATOR
```

```
SRVGRP="identifier"
SRVID="number" CLOPT=" [-A][servopts options] -- -C jobclasses [-n
concurrent_num] [-d]"
```

Description

ARTJESINITIATOR is an Oracle Tuxedo application server provided the TuxJES. It is responsible for invoking the EJR to execute the jobs.

Once a ARTJESINITIATOR is killed or shutdown while it has job running, it will put the job in the INDOUBT state when it is restarted.

Parameters and Options

ARTJESINITIATOR supports the following parameters and options:

-c jobclasses[jobclass]

Specifies the job classes this ARTJESINITIATOR server is associated. If this option is not specified, ARTJESINITIATOR associates with all job classes.

-n concurrent_num

Specifies the number of maximum concurrent executing jobs for this ARTJESINITIATOR server. The default value is 1.

-d

Specifies the number of maximum concurrent executing jobs for this ARTJESINITIATOR server can be change by `artjesadmin changeconcurrent` command.

Example(s)

UBBCONFIG example:

```
ARTJESINITIATOR
SRVID=3 SRVGRP=SYSGRP MIN=10 CLOPT="-A -- -c AHZ"
```

In this example, ten ARTJESINITIATOR instances are configured and are associated with the "A", "H" and "Z" job classes.

See Also

[Oracle Tuxedo Application Runtime for Batch User Guide](#)

ARTJESPURGE

Name

ARTJESPURGE – Purges job queue

Synopsis

```
ARTJESPURGE
SRVGRP="identifier"
SRVID="number" CLOPT=" [-A][servopts options] -- "
```

Description

ARTJESPURGE monitors the purge queue. If it finds a job in the purge queue, it removes the job in the queue and deletes the directory JESROOT/<JOBID>.

See Also

[Oracle Tuxedo Application Runtime for Batch User Guide](#)

TuxJES Queue System

In order to emulate the z/OS JES2 system, TuxJES system uses a queue mechanism for batch job life cycle management. All queues are created in one queue space called "JES2QSPACE". A batch job is represented by a message that resides and is transferred to queues listed in [Table 3](#).

Table 3 TuxJES Queues

Queues	Description
Conversion Queue	When a batch job is submitted to the TuxJES system, it is put in the conversion queue first. There is only one conversion queue in the system. A converted job is moved from the "conversion queue" to the "execution queue". The jobs in the queue are processed in FIFO order. Queue name: CONV
Hold Queue	If a job is in the HOLD state (JCLHOLD or HOLD), it is put in the hold queue. Once released, it is moved to the conversion queue or waiting queue based on the <code>typrun</code> parameter. Queue name: HOLD

Table 3 TuxJES Queues

Queues	Description
Execution Queue	<p>There are 36 job classes (A-Z and 0-9). A job also has a priority value ranging from 0 to 15. The jobs are scheduled based on the job class and priority.</p> <p>One job class is mapped to one /Q queue, (36 queues all together). These are the queues where the job is stored staying and waits for execution. The job priority is mapped to the queue message priority. All queues are created based on priority.</p> <p>Queue names: [A-Z], [0-9].</p>
Executing Queue	<p>This queue stores running/executing jobs. There is only one "executing queue" in the system. When a job is picked up from an "execution queue" and successfully goes to running state, the job is moved to the "executing queue". The jobs in this queue are processed in FIFO order.</p> <p>Queue name: EXEC</p>
Output Queue	<p>When a job is completed or an error occurs, it is sent to the "output queue". There is only one "output queue". The jobs in the queue are processed in FIFO order.</p> <p>Queue name: OUTPUT</p>
Purge Queue	<p>When a job is to be purged, it is moved to the purge queue. There is only one "purge queue" in the system.</p> <p>Queue name: PURGE</p>
Internal Queues	ART JES also has some internal queues on the JES2QSPACE for internal usage.

The TuxJES Queue Creation Script

The TuxJES system provides a sample shell script (`jesqinit`) to create the queue space (`JES2QSPACE`) and the queues listed in [Table 3](#). You can modify the script to adapt to your environment, but must adhere to the following:

1. Queue order can not be changed
2. Fixed queue names and queue space name
3. The script can be customized for queue space/queue creation parameters

Recommended /Q Creation Values

Device Size of Pages: 10000

Queue Space Size of Pages: 5000 (We assume the max number of jobs is 10000, each job will consume 2k bytes and the page size is 4k)

Number of Messages in Queue: 10000

Number of Concurrent Transactions: 1000

Number of Concurrent processes in queue: 100

Note: These parameters can be customized according to the specific environment.

TuxJES User Substitution

JES supports defining the specific OS user to execute jobs. With the Tuxedo User-OS User mapping mechanism, JES system is able to associate the Tuxedo AAA credential adhering to a job with an OS user who has the limited permission to access resources when operating a job.

Terms

[Table 4](#) lists the terms you need to know for a good understanding of the user substitution feature described in this section.

Table 4 User Substitution Terms

Term	Description
Job submitter	The OS user who submits a JES job with <code>artjesadmin</code>
Job owner	The Oracle Tuxedo user who is displayed as the owner of a JES job
Job user	The OS user who submits, cancels or prints a JES job with <code>artjesadmin</code>
Job executor	The OS user who executes the EJRs to execute a JES job

Job Owner Designation in Different Scenarios

The Job owner designated by JES system depends on the combination of configurations on `artjesadmin` and `PRIVILEGE_MODE`. [Table 5](#) shows the relation between job owner designation and different configuration scenarios.

Table 5 Job Owner Designation in Different Configuration Scenarios

Configuration Scenario		Job Owner
When <code>artjesadmin</code> is executed with...	When <code>PRIVILEGE_MODE</code> is set to...	
a profile containing a user name	NONE	Oracle Tuxedo user
a profile containing a user name	<code>USER_IDENTICAL</code> or <code>USER_MAPPING</code>	Oracle Tuxedo user Note: Oracle Tuxedo <code>SECURITY</code> parameter must be set to <code>USER_AUTH</code> , <code>ACL</code> or <code>MANDATORY_ACL</code> , otherwise JES system fails to start up and the following error message is printed into ULOG: "ERROR: The current Tuxedo security level disallow the given privilege mode".
no profile or a profile containing no user name	NONE	* A job with an owner "*" can be controlled by anyone.
no profile or a profile containing no user name	<code>USER_IDENTICAL</code> or <code>USER_MAPPING</code>	<code>artjesadmin</code> fails to login and the following error message is displayed: "ERROR: failed to join application."

Permissions of Job Operations

[Table 6](#) and [Table 7](#) show the permissions of users with different identities when operating jobs in TuxJES system enabling the user substitution.

Table 6 Permissions of Job Operations When PRIVILEGE_MODE is set to "USER_IDENTICAL"

User	Permission
Oracle Tuxedo user "root"	print, hold, release, cancel, purge, and control jobs
Owner of the job	print, hold, release, cancel, purge, and control jobs
Oracle Tuxedo users who have the read and execution permissions to the corresponding job directory	print jobs

Table 7 Permissions of Job Operations When PRIVILEGE_MODE is set to "USER_MAPPING"

User	Permission
Oracle Tuxedo user who is mapped to OS user "root"	print, hold, release, cancel, purge, and control jobs
Oracle Tuxedo user who is mapped to job executer	print, hold, release, cancel, purge, and control jobs
Oracle Tuxedo user who is mapped to a OS user with read and execution permissions to the corresponding job directory	print jobs

Enabling User Substitution in TuxJES

To enable the user substitution in TuxJES, the following operations should be done:

- [Configuring JESCONFIG in TuxJES](#)
- [Booting Up JES System by Root User](#)
- [Configuring Tuxedo UBBCONFIG](#)
- [Configuring File System Permission](#)

Configuring JESCONFIG in TuxJES

The value of `PRIVILEGE_MODE` in `JESCONFIG` should be specified to `MAPPING_CREDENTIAL` or `IDENTITY_CREDENTIAL`.

If the value of `PRIVILEGE_MODE` in `JESCONFIG` is `MAPPING_CREDENTIAL`, the value of `USER_MAPPING_FILE` should be specified and the user mapping file should contain the mapping between Oracle Tuxedo users and OS users.

Booting Up JES System by Root User

When JES is working in SHM mode, it should be booted up by root user.

When JES is working in MP mode, do one of the following:

- Execute `tmboot` by root when JES system is running on the master machine of a MP domain.
- Execute `tlisten` by root when JES system is running on a slave machine of a MP environment.

It is recommended that all machines involved in a JES system use the same NIS system.

Configuring Tuxedo UBBCONFIG

All job users should have full permissions to IPC resource of the JES system.

The `SECURITY` parameter in `RESOURCE` section of `TUXCONFIG` should be `USER_AUTH`, `ACL` or `MANDATORY_ACL`.

Note: If `SECURITY` parameter is set to `APP_PW` and `AUTHSVC` parameter is configured, the `SECURITY` level is regarded as `USER_AUTH` by Oracle Tuxedo.

Here is an example of `UBBCONFIG`:

Listing 2 Oracle Tuxedo UBBCONFIG File Example When Enabling User Substitution in TuxJES System

```
#      (c) 2011 Oracle. All Rights Reserved.
#
*RESOURCES
IPCKEY      <IPCKEY> # for example 132770
DOMAINID    jessample
```

Tuxedo Job Enqueueing Service (TuxJES)

```
MASTER          SITE1
MODEL           SHM
MAXACCESSERS    200
MAXSERVERS      50
NOTIFY          SIGNAL
PERM            0666 #Adding "PERM=0666" in RESOURCES section
SECURITY        USER_AUTH
AUTHSVC         "AUTHSVC"
```

*MACHINES

```
#
```

```
<uname -n>
```

```
LMID = SITE1
TUXDIR = "<full path of TUXEDO software>"
TUXCONFIG = "<full path of APPDIR>/tuxconfig"
TLOGDEVICE = "<full path of APPDIR>/TLOG"
TLOGSIZE=10
APPDIR = "<full path of APPDIR>"
ULOGPFX = "<full path of APPDIR>/ULOG"
```

*GROUPS

```
ARTGRP
```

```
LMID = SITE1  GRPNO = 1
```

```
QUEGRP
```

```
LMID = SITE1  GRPNO = 2
```

```

TMSNAME = TMS_QM TMSCOUNT = 2
OPENINFO = "TUXEDO/QM:<full path of APPDIR>/QUE:JES2QSPACE"

EVTGRP

        LMID= SITE1 GRPNO=3

#

*SERVERS

# Adding RQPERM=0666 RPPERM=0666 in all JES servers entry in SERVERS section
DEFAULT:      CLOPT="-A"

TMUSREVT      SRVGRP=EVTGRP SRVID=1 CLOPT="-A"
               RQPERM=0666 RPPERM=0666

TMQUEUE

        SRVGRP = QUEGRP  SRVID = 1
        GRACE = 0  RESTART = Y CONV = N MAXGEN=10
        CLOPT = "-s JES2QSPACE:TMQUEUE -- -t 5 "
        RQPERM=0666 RPPERM=0666

ARTJESADM      SRVGRP =ARTGRP  SRVID = 1 MIN=1 MAX=1
               CLOPT = "-A -- -i jesconfig"
               RQPERM=0666 RPPERM=0666

ARTJESCONV     SRVGRP =ARTGRP  SRVID = 20 MIN=1 MAX=1
               CLOPT = "-A --"

RQPERM=0666 RPPERM=0666

```

Tuxedo Job Enqueueing Service (TuxJES)

```
ARTJESINITIATOR      SRVGRP =ARTGRP  SRVID =30
                      CLOPT = "-A -- -n 20 -d"
                      RQPERM=0666 RPPERM=0666
```

```
ARTJESPURGE          SRVGRP =ARTGRP  SRVID = 100
                      CLOPT = "-A --"
```

```
AUTHSVR SRVGRP=ARTGRP SRVID=104 CLOPT="-A"
          RQPERM=0666 RPPERM=0666
```

```
*SERVICES
```

Configuring File System Permission

To enable the user substitution successfully, you need to make sure the permission of the file system for users with different identities have been configured to meet the following requirements:

- All job executors should have read and execute permissions to the following folders:
 - \$JESDIR/bin/artjesadmin
 - \$JESDIR/locale/*
 - \$MT_ROOT
- All job executors should have full permissions to the following folders:
 - \$DATA_SOURCE
 - \$DATA
 - \$MT_LOG
 - \$SPOOL
 - \$MT_TMP
 - \$MT_ACC_FILEPATH

- \$JESROOT
- All job users should have read permission to the following folders:
 - \$TUXDIR
 - \$TUXCONFIG

Note: It is recommended that all job executors have the write permission to `ULOG`, `stdout`, and `stderr`, otherwise the log and output messages cannot be written successfully.

Tuxedo Job Enqueueing Service (TuxJES)