

Guide  
August 1997



**WORLD SOFTWARE®**

# Configuration Management

Release  
A8.1

**JDEdwards®**



Item # A81CEACR



J.D. Edwards World Source Company  
8055 E. Tufts Avenue  
Denver, CO 80237

Copyright ©J.D. Edwards World Source Company, 1996, 1997  
All Rights Reserved

The information in this guide is confidential and a proprietary trade secret of J.D. Edwards World Source Company. It may not be copied, distributed, or disclosed without prior written permission. This guide is subject to change without notice and does not represent a commitment on the part of J.D. Edwards & Company and/or its subsidiaries. The software described in this guide is furnished under a license agreement and may be used or copied only in accordance with the terms of the agreement. J.D. Edwards World Source Company uses automatic software disabling routines to monitor the license agreement. For more details about these routines, please refer to the technical product documentation.



## Where Do I Look?



## Guides





## **Important Note for Students in Training Classes**

This guide is a source book for online helps, training classes, and user reference. Training classes may not cover all the topics contained here.



# Welcome

---

## About this Guide

This guide provides overviews, illustrations, procedures, and examples for the current release of J.D. Edwards software. Forms (screens and windows) shown are only examples. If your company operates at a different software level, you might find discrepancies between what is shown in this guide and what you see on your screen.

This guide includes examples to help you understand how to use the system. You can access all of the information about a task using either the guide or the online help.

Before using this guide, you should have a fundamental understanding of the system, user defined codes, and category codes. You should also know how to:

- Use the menus
- Enter information in fields
- Add, change, and delete information
- Create and run report versions
- Access online documentation

## Audience

This guide is intended primarily for the following audiences:

- Users
- Classroom instructors
- Client Services personnel
- Consultants and implementation team members

## Organization

This guide is divided into sections for each major function. Sections contain chapters for each task or group of related tasks. Each chapter contains the information you need to accomplish the task, run the program, or print the

report. Chapters normally include an overview, form or report samples, and procedures.



When it is appropriate, chapters also might explain automatic accounting instructions, processing options, and warnings or error situations. Some chapters include self-tests for your use outside the classroom.

This guide has a detailed table of contents and an index to help you locate information quickly.

## Conventions Used in this Guide

The following terms have specific meanings when used in this guide:

- *Form* refers to a screen or a window.
- *Table* generally means “file.”

We assume an “implied completion” at the end of a series of steps. That is, to complete the procedure described in the series of steps, either press Enter or click OK, except where noted.

# Table of Contents

---

## Overview

### Configuration Management Overview

System Integration .....	1-2
Enterprise Requirements Planning and Execution Review .....	1-4
Terms and Concepts .....	1-6
Analyzing Your Configured Items .....	1-7
Features .....	1-8
Tables .....	1-8
Menu Overview .....	1-10
Training Class Case Study .....	1-11
Example: Entering a Sales Order for a Forklift .....	1-12

## Setup

### Configuration Management Setup

About Configuration Management Setup .....	2-1
Set Up Item Information .....	2-5
Setting Up Item Information .....	2-5
Entering Item Master Information .....	2-5
Entering Branch/Plant Information .....	2-10
Entering a Bill of Material .....	2-14
Entering a Routing .....	2-14
Set Up Distribution Information .....	2-17
Setting Up Distribution Information .....	2-17
Setting Up Line Types .....	2-17
Setting Up Order Activity Rules .....	2-19
Setting Up Price Information .....	2-21
Setting Up Pricing Groups .....	2-23
Setting Up Discounting Information .....	2-25
Set Up Constants .....	2-29
Setting Up Constants .....	2-29
Set Up Segments .....	2-33
Setting Up Segments .....	2-33
Defining a Segment .....	2-35
Setting Up User Defined Codes .....	2-40
Locating Segment Information .....	2-42

Set Up Cross-Segment Editing Rules .....	2-45
Setting Up Cross-Segment Editing Rules .....	2-45
Logic Statements .....	2-45
Error Messages .....	2-45
Setting Up Cross-Segment Logic .....	2-46
Setting Up Custom Error Messages .....	2-56
Reviewing Cross-Segment Editing Information .....	2-57
Understand Derived Calculations .....	2-59
About Derived Calculations .....	2-59
Algebraic Formulas .....	2-60
Segment References .....	2-60
Trigonometric and Logarithmic Functions .....	2-61
Substrings .....	2-62
Concatenations .....	2-62
Referencing External Fields .....	2-63
Referencing External Programs .....	2-64
Calculating Smart Parts .....	2-64
Set Up Assembly Inclusion Rules .....	2-67
Setting Up Assembly Inclusion Rules .....	2-67
Logic Statements .....	2-68
Advanced Assembly Inclusion Rules .....	2-68
Derived Calculations .....	2-69
Understanding Smart Parts .....	2-69
Referencing External Fields .....	2-69
Referencing External Programs .....	2-70
Multi-Level Processing .....	2-70
Referencing Table Names .....	2-70
Defining Assembly Inclusion Rules .....	2-71
Processing Options for Assembly Inclusion Rules .....	2-83
Locating Assembly Inclusion Rules .....	2-83
Understand Tables .....	2-87
About Tables .....	2-87
Example: Multiple Segments, Exact Lock .....	2-89
Example: Multiple Segments, Column Lock .....	2-90
Set Up Tables .....	2-91
About Tables .....	2-91
Setting Up Tables .....	2-91
Setting Up Table Dimensions .....	2-92
Processing Options for Table Definition .....	2-95
Setting Up Configured Item Cross-Reference .....	2-95
Processing Options for Configured Item Cross Reference .....	2-96
Setting Up Table Values .....	2-96
Processing Options for Table Keys .....	2-99
Linking a Table to an Assembly Inclusion Rule .....	2-99
Printing Table Information .....	2-101
Print Reports .....	2-103
Printing Reports .....	2-103
Printing Segment Information .....	2-104
Printing Cross-Segment Editing Rules .....	2-105
Printing Assembly Inclusion Rules .....	2-106

## Sales Orders

### Configured Item Sales Orders

About Sales Orders .....	3-1
Work with Configured Item Sales Orders .....	3-3
Working with Configured Item Sales Orders .....	3-3
Entering a Sales Order in Text Mode .....	3-4
Entering a Sales Order in Assisted Mode .....	3-6
Entering a Sales Order in Assisted Prompt Mode .....	3-9
Working with Error Messages .....	3-14
Reviewing Configured Text .....	3-16
Revising a Sales Order for a Configured Item .....	3-17
Converting Sales Quotes for Configured Items .....	3-19
Processing Options for Sales Order Entry – Detail .....	3-21

## Configured Items

### Configured Items

About Configured Items .....	4-1
Process Work Orders .....	4-3
Processing Work Orders .....	4-3
Processing Options for Work Order Generation .....	4-5
Processing Options for Subsystem Maintenance .....	4-8
Work with Configured String History .....	4-9
Working with Configured String History .....	4-9
Generating the Configured String History .....	4-9
Reviewing the Configured String History .....	4-10
Understand Configured Items and Manufacturing .....	4-13
About Configured Items and Manufacturing .....	4-13
Reviewing Hours and Quantities .....	4-13
Example: Reviewing Hours and Quantities .....	4-14
Working With Manufacturing Accounting and Product Costing .....	4-15
Working with Work Order Completions .....	4-15
Understand Configured Items and Distribution .....	4-17
About Configured Items and Distribution .....	4-17
Working with Configured Item Inventory .....	4-17
Example: Issues .....	4-18
Example: Transfers .....	4-19
Example: Adjustments .....	4-20
Checking Availability .....	4-21
Example: Summary Availability .....	4-22
Example: Detailed Availability .....	4-23
Example: Reviewing Customer Service Information .....	4-24
Working with Pick Lists .....	4-24
Example: Pick Lists .....	4-25

Working with Shipments .....	4-26
Working with Invoices .....	4-27
Example: Invoice .....	4-28

## Appendices

Appendix A – Functional Servers .....	A-1
Example: Voucher Processing Functional Server .....	A-2

## Glossary

## Index

# Overview





# Configuration Management Overview

Many manufacturers sell products that are an arrangement of components that a customer orders. In this environment, a manufacturer assembles a large variety of end products from relatively few components. When customers place orders, they specify features and options about the product.

When you enter a sales order for a configured item, a series of forms appear within which you answer questions about the item's segments (features and options). The system verifies each segment value against user defined information, such as rules and user defined code tables of choices. If the configuration is valid, the system processes the order.

Although setup for Configuration Management can be complex, there are many benefits. During setup you must define the following information:

- Constants
- Segments
- Cross-segment editing rules
- Assembly inclusion rules

However, as a result of using Configuration Management, you can:

- Use fewer end part numbers
- Create dynamic work order parts lists and routings
- Provide for order history and configuration audit trails
- Improve order accuracy
- Shorten leadtimes
- Provide better margin information
- Improve customer service

Examples of manufacturers who typically use Configuration Management include:

- Furniture and fixtures
- Paper products
- Building products
- Commercial printing
- Control and measurement equipment




- Transportation equipment
- Windows and doors
- Other dimensional products

## System Integration

The Configuration Management system works with other J.D. Edwards systems to generate the following for configured items:

- Sales orders
- Parts lists
- Routings
- Work orders
- Price information
- Work order costing
- Invoices



J.D. Edwards also offers kit processing that enables feature and option processing. However, kit processing might not be appropriate for features or complex specifications, such as conditional part requirements. The Configuration Management system is appropriate for items that:

- Are complex
- Require routings that change based on features or options
- Include features that are not compatible with other features
- Require multiple work orders to define an assembly


### **Enterprise Requirements Planning and Execution Review**

Configuration Management is one of many systems in the Enterprise Requirements Planning and Execution system.

Use the Enterprise Requirements Planning and Execution system to coordinate your inventory and labor resources to deliver products according to a managed schedule. It is a closed-loop manufacturing system that formalizes company and operations planning, and the implementation of those plans.

The Enterprise Requirements Planning and Execution system includes the following J.D. Edwards systems:

Enterprise Requirements Planning and Execution



### Terms and Concepts

**Configured item**

A configured item is comprised of different features requested by a customer, for example, a forklift. You associate segments with the configured item. For example, the configured item FORKLIFT-A contains the following segments:

FORKLIFT-A

- Segment 10 (Lift Rating)
- Segment 20 (Power Type)
- Segment 30 (Boom Height)

**Segment**

When you set up a configured item, you define segments to represent characteristics of a configured item, such as an optional paint color or a lift rating. For example:

Segment 10 (Lift Rating)

- 2000 pounds
- 4000 pounds
- 6000 pounds

Segment 40 (Paint)

- STANDARD
- CUSTOM

A segment might also be called a feature or an option.

**Configured string**

During sales order entry, the system joins the segments and expresses the configuration as a string of segments separated by a delimiter. For example:

2000/PROPANE/08/STD/50/3587.4659217

**Multi-level configured item**

You can set up a configured subassembly within a configured item. For example, the configured item FORKLIFT-A contains a configured subassembly for the item BOOM.

---

**Cross-segment editing rules**

Use cross-segment editing rules to establish the relationships between the configured item segments with logic statements. This enables you to avoid invalid combinations and prevent invalid sales orders. The system edits the segments on the sales order against these cross-segment editing rules and error messages appear for information that violates the rules. For example:

*If segment 10 (Lift Rating) = 6000 pounds, then segment 30 (Boom Height) must = 12 (feet) else segment 30 must be  $\leq$  10 (feet).*

**Assembly inclusion rules**

Use assembly inclusion rules to translate requested options and values from sales order entry into the specific components, operations, and calculated values necessary to build and price the configured item. For example:

*If segment 10 = 6000 and segment 30  $\geq$  10, then use part F170, else use part F175.*

## Analyzing Your Configured Items

Before you work with Configuration Management, ensure that you can answer the following questions about your configured items:

- How do customers order the configured item?
- How will the configured item be priced?
- Which components make up the configured items?
- Which routings do the configured items require?
- Which calculations are required to support prices, components, and routing steps?

This information will help you determine the sequence of questions. This is important because you can define levels of questions within multi-level configured items. Knowing this information before you set up this system will save time during setup.

### Features

The Configuration Management system enables you to perform the following functions:

- Specify a variety of features and options with configured item segments
- Establish relationships between options to prevent invalid product configurations
- Define multi-level configured items and multiple associated work orders
- Establish default values or ranges for options and features
- Calculate values for options with algebraic definitions
- Create generic rules that can be used across branch/plants
- Create assembly inclusion rules that control price adjustments, routings, and parts
- Define a table of values that is referenced by assembly inclusion rules

### Tables

The Configuration Management system uses the following tables:

<b>Configured Item Segments (F3291)</b>	Contains the segments for the configured items defined on the Item Master and Branch/Plant
<b>Cross-Segment Editing Rules (F3292)</b>	Defines the relationships among the configured items' segments
<b>Configurator Constants (F3209)</b>	Stores constants that you define to control processing at the branch/plant level
<b>Values Detail (F32921)</b>	Stores the *VALUES definitions for cross-segment editing rules and assembly inclusion rules
<b>Range Detail (F32922)</b>	Stores the *RANGE definitions for cross-segment editing rules and assembly inclusion rules
<b>Assembly Inclusion Rules (F3293)</b>	Stores the components, routings, calculations, and price adjustments for configured items
<b>Configured String History (F3294)</b>	Stores the history for the configured items of all the configurations ordered

---


<b>Configured String Master (F32941)</b>	Contains the configured string identifier for each configuration
<b>Configured String Segments (F32942)</b>	Stores the configured string for each segment
<b>Rules Table Definition (F3281)</b>	Stores table information such as description, table type, number of segments and return values
<b>Configured Item/Rules Table Cross-Reference (F3282)</b>	Defines which segment values reference tables for each configured item
<b>Rules Table Value Definition (F32821)</b>	Defines which segments will be populated with the returned values
<b>Table Detail (F3283)</b>	Stores the actual table values for each combination of segment values that you define for the table
<b>Item Master (F4101)</b>	Stores basic information about each item in inventory, such as item numbers, description, category codes, and units of measure
<b>Branch/Plant (F4102)</b>	Stores branch/plant information, such as quantities and branch level category codes
<b>Item Location (F41021)</b>	Stores primary and secondary locations for an item.
<b>Cost Ledger (F4102)</b>	Stores cost information for an item
<b>Base Price (F4106)</b>	Stores base price information for an item
<b>Sales Order Detail (F4211)</b>	Defines which level of the configured item is related to a component and complete information for each line of the sales order
<b>Sales Order Header (F4201)</b>	Maintains the billing instruction, address, and delivery information for a customer order

### Menu Overview

The J.D. Edwards Configuration Management system uses the following menus.

#### Menu Overview – Configuration Management

Configurator G32



##### Setup Processes

- Configurator Setup G3241



##### Daily Operations

- Configurator G32




##### Advanced and Technical Processes

- Advanced Configurator G3231

## Training Class Case Study


In the case study, a forklift is an example of a multi-level configured item. Its subassemblies include the boom and fork. For the item and each subassembly in the forklift, segments represent features and options.




## Example: Entering a Sales Order for a Forklift

You enter a sales order to record information about your customers and the items they order. When you enter a configured item, the system prompts you to answer option and feature questions to define the correct components, prices, and work orders.

On Sales Order Entry




1. Complete the following required fields and press Enter:
  - Sold To
  - Branch/Plant
  - Quantity
  - Item



## On Configured Item Specifications

2. Do one of the following:
  - To accept the default values, press Enter.
  - To select another value, access Segment Value Selection and select a value.



3. Repeat steps 2 for the remaining segments and lower level items.
4. To process the sales order, press Enter.
5. On Sales Order Entry, locate your sales order to display the price, component item, and configured text information.



# Setup





# Configuration Management Setup

## Objectives

- To identify a configured item
- To set up segments that identify the main features of a configured item
- To set up the relationships among features
- To establish which parts are included on the sales order
- To specify increases or decreases in the price of the configured item based on which options are chosen
- To specify how to manufacture the item by choosing the proper routing steps
- To review configuration information

## About Configuration Management Setup

You must set up the Configuration Management system before you can enter sales orders for configured items.

Setting up Configuration Management consists of the following tasks:

- Setting up item information
- Setting up distribution information
- Setting up constants
- Setting up segments
- Setting up cross-segment editing rules
- Understanding derived calculations
- Setting up assembly inclusion rules
- Understanding tables
- Setting up tables
- Printing reports



You must first set up the following information:

- Configured item information
- Constants
- Segments
- Cross-segment editing rules
- Assembly inclusion rules
- Tables

You set up configured item information for other systems, including:

- Inventory Management
- Pricing Management
- Sales Order Management
- Product Data Management

Configuration Management constants control processing for your business. You can use constants to control:

- Branch/plant-specific information about work order processing
- Sales quote processing
- Availability checking
- Whether calculated segments appear

Segments are the features and options of the configured item. Segments represent product characteristics such as color, material, or size. You assign numbers to each segment of the configured item. The numeric sequence determines the order in which you specify the segment value during sales order entry.

You set up cross-segment editing rules with logic statements to establish the relationship between the segments. Use these rules to prevent invalid configurations during sales order entry. You can define custom error messages for a cross-segment editing rule.

Assembly inclusion rules process requested features from sales order entry into the specific components and routing operations necessary to build the configured item. Different types of assembly inclusion rules allow you to define:

- Components
- Price/cost adjustments
- Routings
- Calculated values

---

You can also set up tables for assembly inclusion rules to reference information that is based on segment values. Table processing might also be referred to as matrix processing. You might define tables for components, prices, and calculated values. Using tables reduces the amount of rules that are required, simplifies rule maintenance, and improves processing time.



# Set Up Item Information

---


## Setting Up Item Information

You must set up item information for your configured item and its components and configured subassemblies. Use programs in the Inventory Management and Product Data Management systems to define item information.

Setting up item information consists of the following tasks:

- Entering Item Master information
- Entering Branch/Plant information
- Entering a bill of material
- Entering a routing

## Entering Item Master Information



From Inventory Management (G41), choose Inventory Master/Transactions

From Inventory Master/Transactions (G4111), choose Item Master Information

You enter Item Master information that is unique to the item across all branch/plants. This includes stocking and pricing information.

You have several options for pricing a configured item. Choose from the following pricing methods:

- Total the list prices of components to determine the configured item price
- Use the list price of the configured item
- Use assembly inclusion pricing rules to determine the price
- Total the discounted price of components

### **▶ To enter Item Master information**

---

On Item Master Information

Complete the following fields:

- Stcking Type
- Line Type
- Inventory Cost Level
- Kit Pricing Method
- Lot Process Type



For the configured item, you must set the Stcking Type to C, and the Inventory Cost Level to 3.

Field	Explanation
2nd Item Number	<p>The system provides three separate item numbers plus an extensive cross-reference capability to alternate item numbers. These item numbers are:</p> <ol style="list-style-type: none"> <li>1. Item Number (short) – An 8-digit, computer-assigned item number.</li> <li>2. 2nd Item Number – The 25-digit, free-form, user defined, alphanumeric item number.</li> <li>3. 3rd Item Number – Another 25-digit, free-form, user defined, alphanumeric item number.</li> </ol> <p>In addition to these three basic item numbers, an extensive cross-reference search capability has been provided (see XRT). Numerous cross-references to alternate part numbers can be user defined (for example, substitute item numbers, replacements, bar codes, customer numbers, or supplier numbers).</p>

Field	Explanation
Stocking Type	<p>A user defined code (41/I) that indicates how you stock an item(for example, as finished goods, or as raw materials). The following stocking types are hard-coded and you should not change them:</p> <ul style="list-style-type: none"> <li>B Bulk floor stock</li> <li>C Configured item</li> <li>F Feature</li> <li>K Kit parent item</li> <li>N Non-stock</li> </ul>
Line Type	<p>A code that controls how the system processes lines on a transaction. It controls the systems with which the transaction interfaces (General Ledger, Job Cost, Accounts Payable, Accounts Receivable, and Inventory Management). It also specifies the conditions under which a line prints on reports and is included in calculations. Codes include:</p> <ul style="list-style-type: none"> <li>S Stock item</li> <li>J Job cost</li> <li>N Non-stock item</li> <li>F Freight</li> <li>T Text information</li> <li>M Miscellaneous charges and credits</li> <li>W Work order</li> </ul>
Inventory Cost Level	<p>A code that indicates whether the system maintains one overall inventory cost for the item, a different cost for each branch/plant, or a different cost for each location and lot within a branch/plant. The system maintains inventory costs in the Inventory Cost table (F4105).</p> <p>Valid codes are:</p> <ul style="list-style-type: none"> <li>1 Item level</li> <li>2 Item/Branch level</li> <li>3 Item/Branch/Location level</li> </ul>
Kit Pricing Method	<p>A code that indicates how the system determines the sales price of a kit or configured item. Valid codes are:</p> <ul style="list-style-type: none"> <li>1 The system totals list prices of components to determine the kit or product family price.</li> <li>2 The list price of the final kit. This is the kit or product family price from the Base Price table (F4106).</li> <li>3 The price inclusion rules for the product family determine the product family price (for configured items only).</li> <li>4 The kit or product family price is the sum of the components' discounted prices. There is no discount on the parent.</li> </ul>

---

Stocking Type	<p>A user defined code (41/I) that indicates how you stock an item(for example, as finished goods, or as raw materials). The following stocking types are hard-coded and you should not change them:</p> <ul style="list-style-type: none"><li>B Bulk floor stock</li><li>C Configured item</li><li>F Feature</li><li>K Kit parent item</li><li>N Non-stock</li></ul>
Line Type	<p>A code that controls how the system processes lines on a transaction. It controls the systems with which the transaction interfaces (General Ledger, Job Cost, Accounts Payable, Accounts Receivable, and Inventory Management). It also specifies the conditions under which a line prints on reports and is included in calculations. Codes include:</p> <ul style="list-style-type: none"><li>S Stock item</li><li>J Job cost</li><li>N Non-stock item</li><li>F Freight</li><li>T Text information</li><li>M Miscellaneous charges and credits</li><li>W Work order</li></ul>
Inventory Cost Level	<p>A code that indicates whether the system maintains one overall inventory cost for the item, a different cost for each branch/plant, or a different cost for each location and lot within a branch/plant. The system maintains inventory costs in the Inventory Cost table (F4105).</p> <p>Valid codes are:</p> <ul style="list-style-type: none"><li>1 Item level</li><li>2 Item/Branch level</li><li>3 Item/Branch/Location level</li></ul>
Kit Pricing Method	<p>A code that indicates how the system determines the sales price of a kit or configured item. Valid codes are:</p> <ul style="list-style-type: none"><li>1 The system totals list prices of components to determine the kit or product family price.</li><li>2 The list price of the final kit. This is the kit or product family price from the Base Price table (F4106).</li><li>3 The price inclusion rules for the product family determine the product family price (for configured items only).</li><li>4 The kit or product family price is the sum of the components' discounted prices. There is no discount on the parent.</li></ul>

---

Reg. or Lot Processing

A code that indicates whether lot or serial number is assigned. Lot and serial number processes use the Lot Master table (F4108).

Valid codes are:

- 0 Lot assignment is optional. You can manually assign numbers. Quantity can be greater than one (default).
- 1 Lot assignment is required. The system assigns numbers using the system date in YYMMDD format. Quantity can be greater than one.
- 2 Lot assignment is required. The system assigns numbers in ascending order using Next Numbers. Quantity can be greater than one.
- 3 Lot assignment is required. You must manually assign numbers. Quantity can be greater than one.
- 4 Serial number assignment is optional except during shipment confirmation. Quantity must not exceed one.
- 5 Serial number assignment is required. The system assigns numbers using the system date in YYMMDD format. Quantity must not exceed one.
- 6 Serial number assignment is required. The system assigns numbers in ascending order using Next Numbers. Quantity must not exceed one.
- 7 Serial number assignment is required. You must manually assign numbers. Quantity must not exceed one.

..... *Form-specific information* .....

Use codes 4 through 7 for advanced serial number processing. In Purchase Management, you add serial numbers using the Lot field on Purchase Order Detail. Each item must have a unique serial number.

For items requiring serial numbers as well as lot assignments, use the Lot Process Type field in conjunction with the Serial No Required field. Codes 3 through 5 for the Serial No Required field indicate the setup requirements necessary for these items.

---

**See Also**

- *Entering Basic Item Information (P4101) in the Inventory Management Guide*

## Entering Branch/Plant Information



From Inventory Management (G41), choose Inventory Master/Transactions

From Inventory Master/Transactions (G4111), choose Item Branch/Plant Information

You enter branch/plant information that is unique to an item for a specific branch/plant. This includes lot and leadtime information.

### ► To enter branch/plant information

On Item Branch/Plant Information

1. Locate your configured item.
2. Complete the following fields:
  - Stocking Type
  - Serial Number Required
  - Lot Status Code
  - Lot Process Type

For the configured end item, you must set the Stocking Type to C.

3. Access Plant Manufacturing Data.

**[41827] - Plant Manufacturing Data**

Branch/Plant: R33

Item Number: FORKLIFT-R      Forklift, New Improved

Order Policy Code: 1      Issue Type Code: 1

Value Order policy:      Planning Code: 2

MFG Leadtime Quantity:      Planning Fence Rule: 4

Accounting Cost Qty:      Fixed/Variable: F

Planning Fence: 999      Leadtime Level: 18

Freeze Fence:      Leadtime Manufacturing:     

Message Display Fence:      Leadtime Cumulative:     

Time Basis: 3      Leadtime Per Unit: 71.43

Queue Hours:      Shrink Factor:     

Setup Labor:      Shrink Factor Method: 5

ECC Reason:      Item Revision Level:     

ECC Number:      Grade Control: 4

ECC Date:      Standard Grade:     

Potency Control: 4      From - Thru Grade: -

Standard Potency:     

From - Thru Potency:     

F3=Exit    F12=Previous    F24=More Keys    MW

4. On Plant Manufacturing Data, complete the following fields:
- Leadtime Level
  - Leadtime Manufacturing
  - Leadtime Cumulative
  - Leadtime Per Unit


<b>Field</b>	<b>Explanation</b>
Serial No. Required	<p>A code that indicates whether you must attach a serial number to this item at the time of receipt or sale for basic serial number processing, or if memo lot information is required for advanced serial number processing.</p> <p>You can use basic serial number processing for informational purposes only. For example, you can add a serial number for an item, and review the number later.</p> <p>For basic serial number processing, valid values are:</p> <ul style="list-style-type: none"> <li>Y Yes, the system requires a serial number for all transactions pertaining to this item in related inventory, sales, and purchase order programs</li> <li>N No, the system does not require a serial number</li> </ul> <p>The system does not use this information if you use advanced serial number processing. Advanced serial number processing allows you to track an item through purchasing and sales based on a serial number. To specify serial number requirements, you must use the Lot Process Type field on Item Master Information.</p> <p>Values 3 through 5 indicate whether lot assignment is required for items with serial numbers. You can require assignment of up to three lot numbers, including Supplier Lot, Memo Lot 1, and Memo Lot 2. To specify lots for items with serial numbers, you must use the following values:</p> <ul style="list-style-type: none"> <li>3 Supplier lot number required (purchasing only)</li> <li>4 Supplier lot number required (purchasing only), and Memo Lot 1 required</li> <li>5 Supplier lot number required (purchasing only), Memo Lot 1 required, and Memo Lot 2 required</li> </ul>
Lot Status Code	<p>A user defined code (table 41/L) that indicates the status of the lot. If you leave this field blank, it indicates that the lot is approved. All other codes indicate that the lot is on hold.</p> <p>You can assign a different status code to each location in which a lot resides on Item/Location Information or Location Lot Status Change.</p>

Field	Explanation
Level Leadtime	<p>A value that represents the leadtime for an item at its assigned level in the production process, as defined on Plant Manufacturing Data. The system uses this value to calculate the start dates for work orders using fixed leadtimes. Level leadtime is different for purchased and manufactured items:</p> <p>You can enter level leadtime manually on Manufacturing Values Entry, or you can use the Leadtime Rollup program calculate it. To calculate level leadtime using the Leadtime Rollup program, you must first enter a quantity in the Manufacturing Leadtime Quantity field in the Item Branch table (F4102).</p>
Manufacturing Leadtime	<p>The total number of days required to build an item from its lowest level components to the final assembly. This value is the total of the level leadtimes for all manufactured items, plus the highest manufacturing leadtime for all its components.</p> <p>If all components are purchased, the manufacturing leadtime equals the item's level leadtime. Purchased item leadtimes are not included in the calculation of manufacturing leadtimes.</p> <p>You can enter the manufacturing leadtime manually or you can have the system calculate it when you run the Leadtime Rollup program.</p>
Cumulative Leadtime	<p>The total number of days required to build an item from its lowest level components to the final assembly. The system calculates the value differently for manufactured and purchased items.</p> <p>Manufactured – The total of all level leadtimes for all manufactured items, plus the highest cumulative leadtime of all its components.</p> <p>Purchased – The item's level leadtime. Purchased item leadtimes are included in the calculation of cumulative leadtimes.</p> <p>You can enter this value manually or you can have the system calculate it when you run the Leadtime Rollup program.</p>
Leadtime Per Unit	<p>The total number of hours required to build one unit as specified on the routing. This value is factored by the time basis code.</p> <p>You can enter this value manually, or you can have the system calculate it when you run the Leadtime Rollup program. The system overwrites this value when you run the Leadtime Rollup program.</p> <p>The system uses this field to calculate start dates for work orders when you use variable leadtimes.</p>

### See Also

- *Entering Branch/Plant Information (P41026) in the Inventory Management Guide*

## Entering a Bill of Material



From Product Data Management (G30), choose Daily PDM Discrete.

From Daily PDM Discrete (G3011), choose Enter/Change Bill of Material.

Although you do not need to create a bill of material for a configured item, you can create a bill of material for the configured item's manufactured components. Assembly inclusion rules define component relationships for configured items. The system adds configured components to sales orders and work orders based on these rules.


During setup, consider creating modular bills of material that group common parts for a specific feature or option. For example, a car might have an interior trim package with two choices, standard or deluxe. Each choice includes specific parts, and might represent two different modular bills.

Although planning bills are not required for Configuration Management, you can use them to help manage demand for specific features and options.

### See Also

- *Working With Bills of Material (P3002) in the Product Management Guide*
- *Reviewing and Revising Simulated Cost Components (P30026) in the Product Costing and Manufacturing Accounting Guide*
- *Entering a Planning Bill (P3002) in the Forecasting Guide*

## Entering a Routing



From Product Data Management (G30), choose Daily PDM Discrete

From Daily PDM Discrete (G3011), choose Enter/Change Routing.

You define all possible routings for the configured item and later use assembly inclusion rules to choose which routing to attach to the work order. The routing assembly inclusion rule allows you to define any complete routing or specific routing operation to attach to a configured item work order. However, you do not need to enter a routing for the configured item's part number.

► **To enter routings**

On Enter/Change Routing



Complete the following fields:

- Item Number
- Branch/Plant
- Work Center
- Operation Sequence Number

Field	Explanation
Branch/Plant	<p>A code that represents a high-level business unit. It can be used to reference a branch or plant that might have departments or jobs, which represent lower-level business units (data item MCU), subordinate to it. For example:</p> <ul style="list-style-type: none"> <li>• Branch/Plant (MMCU)</li> <li>• Dept A (MCU)</li> <li>• Dept B (MCU)</li> <li>• Job 123 (MCU)</li> </ul> <p>Business unit security is based on the higher-level business unit.</p> <p>..... <i>Form-specific information</i> .....</p> <p>The branch/plant in which the routing is located.</p>

<b>Field</b>	<b>Explanation</b>
Work Center	<p>A number that identifies a branch, plant, work center, or business unit.</p> <p>..... <i>Form-specific information</i> .....</p> <p>For Equipment users, this is the craft/resource responsible for completing the maintenance activity.</p>
Oper Seq No	<p>In routings, this number is used to sequence the fabrication or assembly steps in the manufacture of an item. You can track costs and charge time by operation.</p> <p>In bills of material, this number designates the routing step in the fabrication or assembly process that requires a specified component part. You define the operation sequence after you create the routing for the item. The Shop Floor Control system uses this field in the backflush/preflush by operation process.</p> <p>In engineering change orders, this number is used to sequence the assembly steps for the engineering change.</p> <p>Skip To fields allow you to enter an operation sequence that you want to begin the display of information.</p> <p>You can use decimals to add steps between existing steps. For example, use 12.5 to add a step between steps 12 and 13.</p>

### See Also

- *Entering a Routing (P3003) in the Product Data Management Guide*

# Set Up Distribution Information

---

## Setting Up Distribution Information

Before you can enter configured item sales orders, you must provide information that is specific to your business for the Sales Order Management system.

Setting up distribution information consists of the following tasks:

- Setting up line types
- Setting up order activity rules
- Setting up price information
- Setting up pricing groups (optional)
- Setting up discounting information (optional)

## Setting Up Line Types



From Sales Order Management (G42), enter 29

From Sales Order Management Setup (G4241) choose Order Line Types.

You set up line types to generate work orders (in addition to sales orders) for configured items during sales order entry. The W line type generates a work order.

► To set up line types

On Order Line Types

Ln	Description	...Interface...					Rev	Tot	..Include			R	A	E
		G/L	Inv	R/R	R/P	P			Y/N	G/P	C			
T	Sales or Use Tax	Y	N	Y	Y	N	N	N	N	N	N	N	N	N
R	Asset Movements	N	Y	N	N	Y	N	N	N	N	N	N	N	N
B	G/L Account & Item Number-Bulk	Y	B	N	Y	N	N	N	N	N	N	N	Y	N
C	Credit Line	Y	Y	Y	Y	Y	N	Y	N	Y	N	Y	N	N
CS	Consingled Stock	N	Y	Y	Y	N	N	Y	Y	Y	N	N	N	N
CT	Container Transactions	Y	Y	Y	Y	N	N	Y	Y	Y	N	N	N	N
D	Direct Ship Item	Y	D	Y	Y	N	N	N	N	N	N	N	N	N
EA	External Aggregates	Y	Y	Y	Y	N	N	N	N	N	N	N	N	N
EC	Container Deposit/Refund	Y	N	Y	N	N	N	N	N	N	N	N	N	N
F	Freight	Y	N	Y	Y	N	N	N	N	N	Y	N	N	N
IA	Internal Aggregates	Y	B	N	Y	N	N	N	N	N	N	N	N	N
J	G/L Account Number	Y	N	N	Y	N	N	N	N	N	N	N	Y	N
K	Adv. Pricing, Order Level Disc	Y	N	Y	Y	N	N	N	N	N	N	N	N	N
M	Miscellaneous	Y	N	Y	Y	N	N	Y	N	Y	N	Y	N	N
N	Non-Stock	N	N	Y	Y	N	N	Y	N	Y	N	Y	N	N
P	Price Discount	N	N	Y	Y	N	N	Y	N	Y	N	Y	N	N

Complete the following fields:

- Generate Work Order
- Inventory Interface


Field	Explanation
W	A code indicating whether the system automatically generates an internal work order for this line. Valid codes are Y (yes) and N (no, which is the default).

Field	Explanation
Inventory Interface (Y/N)	A code that identifies the type of interface to the Inventory Management system. Valid codes are:
Y	The dollar or unit value of any activity containing this line type will be reflected in inventory. The system also edits the item you enter to ensure that it is a valid item. Y is the default.
A	The number entered will be recognized as a G/L account number. This code is used in purchasing only.
B	The system edits when using format 4 in purchase order entry. The system retrieves price data from the inventory tables, but does not update to the quantity on the purchase order. This code is valid only when the G/L Interface field is Y (yes). Budget checking is fully functional with this interface type.
D	The item in this line is an inventory item that will not affect availability or quantities.
N	This item is not an inventory item.

### See Also

- *Setting Up Order Line Types (P40205) in the Sales Order Management Guide*

## Setting Up Order Activity Rules




From Sales Order Management (G42), enter 29

From Sales Order Management Setup (G4241) choose Order Activity Rules.

You can set up order activity rules before you enter sales orders for configured items to define the specific steps in the sales order processing cycle for your business. A typical sales order cycle includes sales order entry, packing, shipping, and invoicing. For a work order-generated line item and sales order document type, you can add steps to the cycle for creating the work order parts lists and completing work orders for configured items. Both of these manufacturing processes can optionally update associated sales order activity.

### ► To set up order activity rules

On Order Activity Rules



Complete the following fields:

- Order Type
- Line Type
- Status
- Next Status

Field	Explanation
Order Type	<p>A user defined code (00/DT) that identifies the type of document. This code also indicates the origin of the transaction. J.D. Edwards has reserved document type codes for vouchers, invoices, receipts, and time sheets, which create automatic offset entries during the post program. (These entries are not self-balancing when you originally enter them.)</p> <p>The following document types are defined by J.D. Edwards and should not be changed:</p> <ul style="list-style-type: none"> <li>P Accounts Payable documents</li> <li>R Accounts Receivable documents</li> <li>T Payroll documents</li> <li>I Inventory documents</li> <li>O Purchase Order Processing documents</li> <li>J General Accounting/Joint Interest Billing documents</li> <li>S Sales Order Processing documents</li> </ul>

Field	Explanation
Line Type	<p>A code that controls how the system processes lines on a transaction. It controls the systems with which the transaction interfaces (General Ledger, Job Cost, Accounts Payable, Accounts Receivable, and Inventory Management). It also specifies the conditions under which a line prints on reports and is included in calculations.</p> <p>Codes include:</p> <ul style="list-style-type: none"> <li>S Stock item</li> <li>J Job cost</li> <li>N Non-stock item</li> <li>F Freight</li> <li>T Text information</li> <li>M Miscellaneous charges and credits</li> <li>W Work order</li> </ul> <p>..... <i>Form-specific information</i> .....</p> <p>Header field: Use this field to help define an inquiry. You can enter a specific code or you can enter an asterisk (*) to indicate all line types.</p> <p>Detail field: The code identifying the line type of the order activity rule.</p>
Stat	A user defined code (system 40/type AT) that indicates the status of the line.
Stat	A user defined code (40/AT) that indicates the next step in the order process.

**See Also**

- *Setting Up Order Activity Rules (P40204)* in the *Sales Order Management Guide*

**Setting Up Price Information**



From Sales Order Management (G42), choose Price Management

From Price Management (G4222) choose Base Price Revisions

After you have defined the pricing method on Item Master Information, you must define base prices for the components and the configured item. The system uses the base price to price the item. If you define special pricing or discounts for the item, the system bases the calculation of the discounted price on the base price.

For price method codes 1, 2, and 3, you can apply discounts to the configured item. For price method code 4, you can apply discounts to the configured item's components. You can define price adjustment assembly inclusion rules for all price method codes.

The price method code determines whether to price components or parent items. Use base pricing to define prices for:

- An item or group of items
- A specific time period
- Different units of measure
- Different currencies

You can also use advanced pricing schedules for configured items in association with the price method code. However, advanced pricing does not support placing a new line item on the sales order, for example, for free items.

### ► To set up base price information

---

On Base Price Revisions

Cur Cod	UR	Unit Price	Effective From	Effective Thru
USD	ER	48.508,0800	20.01.95	31.12.10

Complete the following fields:

- Item Number
- Branch/Plant
- Currency Code

- UM
- Unit Price
- Effective From
- Effective Thru

Field	Explanation
Cur Cod	A code that indicates the currency of a customer's or a supplier's transactions.
UM	A user defined code (00/UM) that indicates the quantity in which to express an inventory item, for example, CS (case) or BX (box).
Unit Price	The list or base price to be charged for one unit of this item. In sales order entry, all prices must be set up in the Base Price table (F4106).
From	The date on which a transaction, text message, contract, obligation, or preference becomes effective. ..... <i>Form-specific information</i> ..... The date on which this price becomes effective.
Thru	The date on which a transaction, text message, agreement, obligation, or preference has expired or been completed. ..... <i>Form-specific information</i> ..... The date on which this price expires.

**See Also**

- *Defining Base Prices (P4106) in the Sales Order Management Guide*
- *Price and Adjustment Schedule (P4070) in the Advanced Pricing Guide*
- *Entering Basic Item Information (P4101) in the Inventory Management Guide*


**Setting Up Pricing Groups**

Use pricing groups to group items or customers with similar characteristics. This streamlines the processes of entering and maintaining base prices.

Setting up pricing groups consists of the following tasks:

- Set up item price groups
- Set up customer price groups


► **To set up item price groups**



From Sales Order Management (G42), choose Price Management

From Price Management (G4222), choose Define Item Price

On Define Item Price Groups




Complete the following required field:

- Price Group

Field	Explanation
Item Price Group	<p>A user defined code (40/PI) that identifies an inventory price group for an item.</p> <p>Inventory price groups have unique pricing structures that direct the system to incorporate discounts or markups on items on sales and purchase orders. The discounts or markups are based on the quantity, dollar amount, or weight of the item ordered. After you assign a price group to an item, the item uses the same pricing structure that was defined for the inventory price group.</p> <p>You must assign an inventory price group to the supplier or customer, as well as to the item, for the system to interactively calculate discounts and markups on sales orders and purchase orders.</p>

► **To set up customer price groups**



From Sales Order Management (G42), choose Price Management

From Price Management (G4222), choose Define Customer Price Groups

On Define Customer Price Groups


Complete the following required field:

- Price Group

### See Also

- *Setting Up Customer Price Groups (P4092) in the Sales Order Management Guide*

## Setting Up Discounting Information




From Sales Order Management (G42), choose Price Management

From Price Management (G4222), choose Inventory Pricing Rules

After you set up base prices or rules based pricing, you can define how to apply discounts or markups for different circumstances.

► **To set up discounting information**

On Inventory Pricing Rules



Complete the following fields:

- Pricing Rule
- Pricing Method
- Level
- Up To Quantity
- Basis
- Factor Value
- Factor Value Type (%/\$)
- Override Price
- Effect Date
- Expire Date
- Description

Field	Explanation
Pricing Method	<p>A user defined code (system 42, type CT) that indicates the basis for the price rule. Valid values are:</p> <ul style="list-style-type: none"> <li>P Purchase order discounts</li> <li>O Order repricing</li> <li>R Line repricing (basket repricing)</li> </ul>
Pricing Rule	<p>User defined code (table 40/PI) used to classify inventory by pricing rules. Typically, these categories correspond to the major sections in the inventory price book. You can set up as many detail categories as you need. A single code can be used for sales, purchasing, order/basket, and contract pricing. If you set up a contract rule, it must equal the short number for the item under contract.</p>
Lvl	<p>An alphanumeric code that determines the sequence in which the system displays the rules within the pricing group. You define levels when you set up the pricing groups.</p>
Up To Quantity	<p>The volume or quantity breaks commonly used in pricing tables. If the quantity shown on the first level of a rule is 5, then the pricing logic shown on this level applies only to sales of five or fewer items. If the quantity shown in the next level is 10, then the pricing logic applies to sales of 6 through 10 items. 99,999,999 indicates all quantities.</p>
Basis	<p>A costing method on which the system bases the order's net price.</p> <p>The following codes are valid for pricing and repricing:</p> <ul style="list-style-type: none"> <li>1 Last-In Cost</li> <li>5 Future Cost</li> <li>P Unit Price</li> <li>2 Average Cost</li> <li>6 Lot Cost</li> <li>3 Memo Cost 1</li> <li>7 Standard Cost</li> <li>4 Current Cost</li> </ul> <p>The system uses the method you enter here to determine the order's net price.</p> <p>In sales order repricing, the system bases all reprice calculations on either the unit cost or price in the sales detail. Specify P if you want the system to use unit price in the sales order as the basis for reprice calculations. Otherwise, specify a value between 1 to 8 to use the unit cost in the sales detail as the base on value for all reprice calculations.</p>

<b>Field</b>	<b>Explanation</b>
Factor Value	The discount that the system uses when it calculates the price of an item attached to this inventory pricing rule. Discounts can be expressed as multipliers, additional amounts, or deductible amounts. For example, a 10% discount would be expressed as .90. You can use the same factor for markups over cost. For example, a 10% markup would be expressed as 1.10.
Factor Value – Type	A code that indicates whether the factor value is a multiplier (%) or an additional/deductible cash amount (&) when applied to an order's price.
Override	Any price you enter here overrides all other rules or prices.
Effective Date	The date on which a level within a pricing method takes effect. There can be multiple records within a pricing method that have the same level identifier, discount percentage, and so forth, with the only difference being the effective date. This may occur due to special promotion periods.
Expire Date	The date a particular pricing level within a pricing method expires. Within a pricing method there might be multiple records that have the same level identifier, discount percentage and so forth, but have different expiration dates. This might occur due to special promotion periods.
Desc	The descriptive name used to identify a particular discount.


### See Also

- *Defining Price Adjustments (P4271)* in the *Sales Order Management Guide*

# Set Up Constants

---

## Setting Up Constants



From Configurator (G32), enter 29

From Configurator Setup (G3241), choose Configurator Constants

Use constants to control Configuration Management processing for your branch/plants. For each branch/plant, you can:


- Control whether parts lists and routings are attached to work orders with batch or subsystem processing
- Define the configured string delimiter
- Whether the calculated segments appear during sales order entry
- Perform parent availability checking during sales order entry
- Cost sales quotes with manufacturing labor and overhead
- Define which stocked line type to use if the system finds a matching configuration in stock during sales order entry
- Indicate sales quote document types
- Define the status code beyond which changes to the sales order will result only in a status change to the associated work order

The system stores constants in the Configured Constants table (F3209).

### ► To set up constants

---

On Configurator Constants



1. Locate the branch/plant.
2. Complete the following fields:
  - Parts List/Routing
  - Segment Delimiter
  - Check Availability
  - In Stock Line Type
  - Quote Document Type List
  - Cost Sales Quotes
  - Work Order Status for Changes
  - Display Calculated Segments

Field	Explanation
Segment Delimiter	<p>A character separator for configured item sales order entry. The default character is a forward slash (/). This character must be the same for each branch/plant.</p> <p>Notes:</p> <ul style="list-style-type: none"> <li>• Although you can define a different character, do not use an asterisk (*).</li> <li>• Do not change this value after you have established it.</li> <li>• The segment delimiter should not be part of an answer to a segment question.</li> </ul>
Parts List/Routing	<p>Controls whether the parts list and routing for configured item work orders will be created using subsystem or batch processing. Both methods use the Order Processing DREAM Writer (P31410) to write parts list and routing records.</p> <p>Valid values are:</p> <ol style="list-style-type: none"> <li>1 Batch processing. You must run the Order Processing program and change the selection options to accommodate the different sales order numbers being processed. You can also select orders based on their work order status.</li> <li>2 Subsystem processing. After you start the subsystem, the Order Processing program automatically processes any new work orders generated from a configured item sales order. Subsystem processing involves less user interaction and does not generate shop floor paperwork.</li> </ol>
Check Availability (Y/N)	<p>Indicates whether to verify that a configured parent item is in stock during sales order entry. The default value is Y.</p> <p>The system searches inventory for a configuration that matches the parent item during sales order update. If more than one of the item is located, a window displays all matching locations, lots, and their available quantities. From the window, you can select an item to hard commit during the update. If one item is located, the item is hard committed to inventory during the update.</p>

Field	Explanation
In Stock Line Type	<p>A code that controls how the system processes lines on a transaction. It controls the systems with which the transaction interfaces (General Ledger, Job Cost, Accounts Payable, Accounts Receivable, and Inventory Management). It also specifies the conditions under which a line prints on reports and is included in calculations.</p> <p>Codes include:</p> <ul style="list-style-type: none"> <li>S Stock item</li> <li>J Job cost</li> <li>N Non-stock item</li> <li>F Freight</li> <li>T Text information</li> <li>M Miscellaneous charges and credits</li> <li>W Work order</li> </ul>
Quote Document Type List	<p>The Sales Quote Document Type List is a user defined code table (32/QL) that is used to define valid document types for sales quotes in your company. For example, you could define sales quote document types by branch/plant or by type of quote, such as corporate or seasonal quotes.</p>
Cost Sales Quotes (Y/N)	<p>Indicates which costs are accumulated when the Order Type matches one of the Sales Quote Document Types.</p> <ul style="list-style-type: none"> <li>Y All costs from all rules are accumulated. This is the default value.</li> <li>N Only the costs of the P rules are accumulated.</li> </ul>
WO Status for Changes	<p>This field determines the value of the work order status field (user defined code 00/SS) for a configured item. Sales Order Entry has processing options that determine the beginning status and the change status of a work order for a configured item. The processing options work as follows:</p> <ul style="list-style-type: none"> <li>• If the current status of the work order is greater than or equal to the work order change status, the system enters the code value from the change status processing option into the status field on the work order.</li> <li>• If the current status of the work order is less than the work order change status, the system enters the code value from the beginning status processing option into the status field on the work order.</li> </ul>
Display Calculated Segments	<p>Indicates whether calculated segments will display during sales order entry. If this value is N, segments will not display when entering a sales order, however, the value of the segment will be stored in history. If entering a multi-level configured item, levels that have only calculated segments will not display. The default value is N.</p>

# Set Up Segments

---

## Setting Up Segments

A segment is a feature of a configured item, such as color, size, fabric, or power type. You assign segments for the configured item in a numeric sequence. This sequence determines the order in which you provide information about each configured item during sales order entry.

For example, FORKLIFT-A contains the following segments:

- 10 Lift Rating
- 20 Power Type
- 30 Boom Height
- 40 Paint
- 50 Propane Tank
- 60 Calculated Counterweight

During sales order entry you can enter a value for each segment. This value can be restricted by:

- Numeric or alphabetic checking
- Range checking
- User defined code table containing all valid answers

You use segments to define cross-segment editing rules that ensure valid configurations. During sales order entry, the system checks the combination of features and options to ensure that the item can be manufactured.

You use segments to define assembly inclusion rules that determine configuration-specific prices, components, calculated values, and routing steps.

You can define three types of segments:

- Required** During sales order entry, you must provide this required information. For required segments, you can define a table of values, a range of values, or alphanumeric conditions to perform edit checking during sales order entry.

**Optional** During sales order entry, this information is optional. For optional segments, you can define a table of values, a range of values, or alphanumeric conditions to perform edit checking during sales order entry.

**Calculated** During sales order entry, the system calculates the value for this segment. You define the calculation with assembly inclusion rules.



The segment information for a configured item should be the same across branch/plants to allow transfers to other branches.

Setting up segments is the starting point for Configuration Management. You must know information about each segment to determine the configured item's price and to manufacture the item.

Setting up segments consists of the following tasks:

- Defining a segment
- Setting up user defined codes (optional)
- Locating segment information (optional)

### Before You Begin

- Verify that the stocking type for a configured item is C (configured). For more information, see *Entering Basic Item Information (P4101)* in the *Inventory Management Guide*.
- Verify that the manufactured configured components have bills of material. For more information, see *Working with Bills of Material (P3002)* in the *Product Data Management Guide*.
- Create routings for the configured item and for the components that are manufactured. For more information, see *Entering a Routing (P3003)* in the *Product Data Management Guide*.
- Set the pricing method on Item Master Information. For more information, see *Entering Basic Item Information (P4101)* in the *Inventory Management Guide*.

## Defining a Segment



From Configurator (G32) enter 29

From Configurator Setup (G3241) choose Configured Item Segments

To begin using the Configuration Management system, you must define the segments of each configured item. Both cross-segment editing rules and assembly inclusion rules use segments within logic statements.

### ► To define a segment


On Configured Item Segments

Seg	Description	Req	User Codes	Num Y/N	Default Value
10	Lift Rating	R	32	LN Y	4000
20	Power Type	R	32	PT N	GRS
30	Boom Height	R	32	BH Y	10
40	Paint	O	32	PN N	STD
50	Propane Tank	O	32	TK N	
60	Calculated Counterweight	C		Y	

- Complete the following fields:
  - Branch/Plant
  - Configured Item
  - Text String
  - Display Item
  - Segment
  - Description
  - Required
  - Numeric Y/N
- Complete the following optional fields:

## Configuration Management

- User Codes
  - Default Value
3. Access the detail area.



4. Complete the following optional fields:
- Lower Value
  - Upper Value
  - Number of Spaces Before
  - Number of Spaces After
  - Print Segment Number
  - Print Segment Description
  - Print Value
  - Print Value Description
  - Save Segment
  - Return to New Line
  - Derived Calculation Rounding
  - Update Category Code

Field	<p>Explanation</p> <p>Valid values are:</p> <p>Y Indicates that the answer is numeric and therefore, should be right-justified.</p> <p>N Indicates that the answer is alphanumeric and, therefore, should be left-justified.</p>
Required or Optional	<p>Indicates whether a segment is required or optional in a configuration, or whether it must be calculated to specification when entering a sales order.</p> <p>Valid codes are:</p> <p>R Segment answer is required during sales order entry.</p> <p>O Segment answer is optional during sales order entry.</p> <p>C Segment is calculated during sales order entry. You define the calculation with assembly inclusion rules.</p>
Description	<p>A brief description of an item, a remark, or an explanation.</p> <p>..... <i>Form-specific information</i> .....</p> <p>On this screen, the description is of one of the segments for that product family. You can enter a description of the segment, or you can leave the field blank and the system will insert the default description from the user defined codes.</p>
Lower Value	<p>The lower allowed value of this specific segment. If you enter a value here, then you must also enter an upper allowed value.</p>
Upper Value	<p>The upper allowed value of this specific segment. If you enter a value here, then you must also enter a lower allowed value.</p>
No. of Spaces Before	<p>The number of spaces that should print before the segment information in the user defined format.</p>
After	<p>The number of spaces that should print after the segment information in the user defined format.</p>
Print Segment Number	<p>This field determines if the segment number should print on the sales order (Pick Slip and Invoice Print) and work order (Print Parts List).</p> <p>Valid values are:</p> <p>Y or 1 Print on both sales and work order</p> <p>N or 0 Do not print on sales and work order</p>

---

Print Segment Description	<p>This field determines if the segment description should print on the sales order (Pick Slip and Invoice Print) and work order (Print Parts List).</p> <p>Valid values are:</p> <p>Y or 1 Print on both sales and work order</p> <p>N or 0 Do not print on sales and work order</p>
Print Value	<p>This field determines if the segment value should print on the sales order (Pick Slip and Invoice Print) and work order (Print Parts List).</p> <p>Valid values are:</p> <p>Y or 1 Print on both sales and work order</p> <p>N or 0 Do not print on sales and work order</p>
Return to New Line	<p>This field will control whether or not a new line should be started after the segment information is printed. The Configurator Segment Delimiter from the Branch/Plant Constants will print if a new line is not started.</p> <p>Y or 1 Start new line after segment information</p> <p>N or 0 Continue printing on same line</p>
Configurator Print Segmt Value Descript	<p>This field determines if the segment value description from an associated UDC table should print on the sales (Pick Slip and Invoice Print) and work order (Print Parts List).</p> <p>Valid values are:</p> <p>Y or 1 – Print on both sales and work order.</p> <p>N or 0 – Do not print on sales and work order.</p>
Derived Calc Rnd	<p>This field will be used to indicate how many positions to the right of the decimal a derived calculation should be rounded.</p> <p>For example,</p> <ul style="list-style-type: none"><li>• If the result of a derived calculation is 2190.123456789, enter 0 to round to the whole number 2190.</li><li>• Enter 4 to round up to 2190.1235.</li><li>• Leave the Derived Calculation Round field blank to avoid rounding.</li></ul> <p>The system rounds up by one any digit followed by 5 through 9. The system does not round any digit followed by 0 through 4.</p>

---

## What You Should Know About

<b>Multi-level items</b>	You can define multi-level configured items with up to 10 levels. You use assembly inclusion rules to define item levels, and associated work orders.
<b>Setting up generic branch/plants</b>	<p>You can define segments, rules, and configured items that are specific to a branch/plant or generic across all branch/plants. A blank Branch/Plant field identifies a generic branch/plant.</p> <p>If you define generic branch/plants segments, you must also define generic cross-segment editing and assembly inclusion rules.</p> <p>If you don't use the generic branch/plants, then segment information should be the same across branch/plants.</p>
<b>Sequence</b>	You must enter configured item segments in the sequence that you want to prompt the user for information during sales order entry.
<b>Configured item text</b>	You can choose the format for displaying configured item text. You can display the configured string or use the detail area to create custom text that prints on sales orders, work orders, pick lists, and invoices.
<b>Calculated segments</b>	If you define a segment as calculated, you do not need to enter user defined codes or define range checking. Use assembly inclusion rules to define the calculation for that segment. Calculated segments can be numeric or alpha numeric.
<b>Deleting segments</b>	You cannot delete a configured item segment if cross-segment editing or assembly inclusion rules exist for that configured item.
<b>Adding new segments</b>	When you add new segments to an existing configured item, enter them at the end of the list of existing segments.
<b>Updating category codes</b>	You can specify which work order category code will be populated with the segment value during sales order entry.

## See Also

- *Setting up Assembly Inclusion Rules (P3293)*

## Setting Up User Defined Codes



From Configurator (G32), enter 29

From Configurator Setup (G3241), choose Configured Item Segments

From the Configurator Setup menu (G3241), choose Configured Item Segments.


You can create a user defined code table of segment values for a non-calculated segment. This task is optional. During sales order entry, if you have associated a required segment with a user defined code table, you must select a value from the table. If you have associated an optional segment with a user defined code table, you can enter either no value, or a value from the user defined code table.

### ► To set up user defined codes


---

On Configured Item Segments

1. Access User Defined Code Revisions.



2. On User Defined Code Revisions, access User Defined Code Types.



3. On User Defined Code Types, complete the following fields:

- System Code
- User Code
- Description
- Code Length
- 2nd Line
- Code Numeric

You can use codes 55 through 59 for Configuration Management user defined code types.

4. Access User Defined Code Revisions.


5. On User Defined Code Revisions, complete the following fields:

- Code
- Description

Field	Explanation
User Code	Identifies the table that contains user defined codes. The table is also referred to as a code type.  ..... <i>Form-specific information</i> .....
	Identifies the table that contains values.

Field	Explanation
Description	This window will allow you to enter specific values for the segments making up a configured item. Segment values are separated by a special character, called the segment delimiter.
Code Length	The length of the user defined code. It cannot be greater than 10 characters.  ..... <i>Form-specific information</i> .....  The length of the user defined code. It cannot be greater than 10 characters. Do not change the code length without a program change.
2nd Line (Y/N)	A response of Y or M will allow the entry of two lines of User Defined Codes in the revisions screen. A Y will also enable the User Defined Codes window to display a second line of description.  M is for maintenance only for second line display. This capability is seldom used, but has applicability in areas such as inventory product codes. The M value will not display the second line of description in the User Defined Codes window.

## Locating Segment Information



From Configurator (G32), enter 29

From Configurator Setup (G3241), choose Segment Where Used

For the user defined code table that you specify, you can locate all configured items and segments that reference the table. This is useful for reviewing the effect of table changes on configured items.

- *Printing Reports (P32910)*

### ▶ To locate segments

---

On Segment UDC Where Used

Configured Item	Branch/Plant	Seg	Segment Description
FORKLIFT	R30	18	Lift Rating
FORKLIFT-B	R30	18	Lift Rating

Complete the following fields:

- Branch/Plant
- System Code
- User Defined Code

### See Also

- *Printing Reports*



### Exercises

See the exercises for this chapter.



# Set Up Cross-Segment Editing Rules

---

## Setting Up Cross-Segment Editing Rules

To ensure feature and option compatibility during sales order entry, use cross-segment editing rules to establish the relationships between the configured item segments with logic statements. This enables you to avoid invalid combinations of segments and prevent invalid sales orders. Error messages about invalid configurations appear based on segment information from the sales order and cross-segment editing rules.

### Logic Statements

For each cross-segment editing rule, you can define an “if/then/else” logic statement for many conditions. For example, a forklift might require a different value for segment 30 (boom height), depending on the value of segment 10 (lift rating). The following cross-segment editing rule illustrates:

*If* segment 10 (lift rating) = 6000 pounds, *then* segment 30 (boom height) must = 12 (feet) *else* segment 30 must be <= 10 (feet).

### Error Messages

As you enter a sales order, error messages appear for invalid combinations defined by cross-segment editing rules. You can define custom messages or the system can generate an error message. You have two options for controlling how error messages appear:

#### **Custom messages**

Create error messages for your rules that contain specific or custom information instead of the system-generated message. If a custom message exists for a rule, the system highlights the option column. For example:

A 6000 LB capacity Forklift requires a gas or propane engine.

**System messages**

A system-generated message contains the cross-segment editing rule that has been violated. For example:

```
IF Power Type {Seg. 020} is not equal to PROPANE THEN  
Propane Tank {Seg. 050} Should Be equal to *BLANK.  
Power Type {Seg. 020} is WARP. Propane Tank {Seg. 050} is  
50LBTK.
```

Hard or soft error messages might appear:

**Soft error message**

For an invalid combination with an optional condition, a soft error message appears. You can either correct the segment value or override the error message, and continue configuring the item.


**Hard error message**

For an invalid combination with a required condition, a hard error message appears. To proceed, you must correct the problem by changing segment answers.

Setting up cross-segment editing rules consists of the following tasks:

- Setting up cross-segment logic
- Setting up custom error messages
- Reviewing cross-segment editing rule information

## Setting Up Cross-Segment Logic



From Configurator (G32), enter 29

From Configurator Setup (G3241), choose Cross Segment Editing

Setting up cross-segment logic consists of the following tasks:


- Setting up logic statements
- Setting up values
- Setting up ranges
- Copying a rule

► To set up logic statements

On Cross Segment Editing

IF Condition				THEN Segment Restriction						
H	D	Seg	Rel	Value	Seg	Req	Rel	Value	Text	P
I		10	EQ	6000	20	R	EQ	#VALUE	Y	
				Next Edit Group						
I	(	10	LE	4000					N	
		20	EQ	BATTERY	)	30	R	LE	10	Y
				Next Edit Group		30	R	LE	12	Y
I	(	10	EQ	6000					N	
		20	EQ	PROPANE	)	50	R	EQ	50	N
				Next Edit Group						
I		20	NE	PROPANE		50	D	EQ	#BLANK	Y
				Next Edit Group						

- Complete the following fields:
  - Branch/Plant
  - Configured Item
  - And/Or
  - Bracket Selection Beginning
  - Segment
  - Relationship
  - Value
  - Bracket Selection Ending
  - Segment
  - Required/Optional
  - Relationship
  - Value
  - Custom Text
- Access the detail area.



3. Complete the following optional fields:

- Segment Item
- Segment Branch

Field	Explanation
Branch/Plant	<p>A number that identifies a branch, plant, work center, or business unit.</p> <p>..... <i>Form-specific information</i> .....</p> <p>You can define a generic or blank branch/plant for cross segment editing rules and then use the rules for all branch/plants.</p>
Configured Item	<p>A number that the system assigns to an item. It can be in short, long, or 3rd item number format.</p> <p>..... <i>Form-specific information</i> .....</p> <p>Header: The configured item number for which cross segment editing rules are being defined.</p> <p>Detail: The configured item number of the segment in the cross segment editing rules. This is used to reference a previously selected segment.</p>

Field	Explanation																
And/Or Selection	<p>A code that determines whether compound data selection logic is based on an A = AND condition or an O = OR condition.</p> <p>..... <i>Form-specific information</i> .....</p> <p>For configuration management, additional values include:</p> <table data-bbox="776 447 915 537"> <tr><td>I</td><td>If</td></tr> <tr><td>E</td><td>Else</td></tr> <tr><td>*</td><td>Then</td></tr> </table>	I	If	E	Else	*	Then										
I	If																
E	Else																
*	Then																
Relationship	<p>The relationship between the range of variances you display. Valid codes are:</p> <table data-bbox="776 625 1133 873"> <tr><td>EQ</td><td>Equal to</td></tr> <tr><td>LT</td><td>Less than</td></tr> <tr><td>LE</td><td>Less than or equal to</td></tr> <tr><td>GT</td><td>Greater than</td></tr> <tr><td>GE</td><td>Greater than or equal to</td></tr> <tr><td>NE</td><td>Not equal to</td></tr> <tr><td>NL</td><td>Not less than</td></tr> <tr><td>NG</td><td>Not greater than</td></tr> </table>	EQ	Equal to	LT	Less than	LE	Less than or equal to	GT	Greater than	GE	Greater than or equal to	NE	Not equal to	NL	Not less than	NG	Not greater than
EQ	Equal to																
LT	Less than																
LE	Less than or equal to																
GT	Greater than																
GE	Greater than or equal to																
NE	Not equal to																
NL	Not less than																
NG	Not greater than																
Relationship	<p>A code the identifies the operands in Boolean logic. You can specify any of the following:</p> <table data-bbox="776 961 1133 1209"> <tr><td>EQ</td><td>Equal to</td></tr> <tr><td>LT</td><td>Less than</td></tr> <tr><td>LE</td><td>Less than or equal to</td></tr> <tr><td>GT</td><td>Greater than</td></tr> <tr><td>GE</td><td>Greater than or equal to</td></tr> <tr><td>NE</td><td>Not equal to</td></tr> <tr><td>NL</td><td>Not less than</td></tr> <tr><td>NG</td><td>Not greater than</td></tr> </table>	EQ	Equal to	LT	Less than	LE	Less than or equal to	GT	Greater than	GE	Greater than or equal to	NE	Not equal to	NL	Not less than	NG	Not greater than
EQ	Equal to																
LT	Less than																
LE	Less than or equal to																
GT	Greater than																
GE	Greater than or equal to																
NE	Not equal to																
NL	Not less than																
NG	Not greater than																
Txt Message	<p>Indicates whether to display the custom message.</p> <p>Valid values are:</p> <table data-bbox="776 1314 1295 1377"> <tr><td>Y</td><td>Custom message will be displayed</td></tr> <tr><td>N</td><td>Custom message will not be displayed</td></tr> </table> <p>If this value is Y with a segment and condition, it will only appear when that condition is false instead of the standard cross segment error message appearing.</p>	Y	Custom message will be displayed	N	Custom message will not be displayed												
Y	Custom message will be displayed																
N	Custom message will not be displayed																
Seg Item	<p>A number that the system assigns to an item. It can be in short, long, or 3rd item number format.</p> <p>..... <i>Form-specific information</i> .....</p> <p>Header: The configured item number for which cross segment editing rules are being defined.</p> <p>Detail: The configured item number of the segment in the cross segment editing rules. This is used to reference a previously selected segment.</p>																

Field	Explanation
Seg Branch	This branch represents the branch of the segment's configured item number. Use this value to reference a previously selected segment from a different configuration level.
Bracket Selection Beginning	<p>A collection of open and closed brackets to group conditional configurator rules.</p> <p>For example, to define the condition (Seg 1 = A OR Seg 2 = B) AND Seg 3 = C, use the following brackets:</p> <p>(Seg 1 = A O Seg 2 = B) A Seg 3 = C</p>
Configurator If Selection Value	<p>Indicates an "if" logic relationship for configuration rules. You can enter a specific UDC value or one of the following values:</p> <p><b>*VALUES</b> Enter up to 45 values on a separate window. NOTE: When you specify *VALUES in different versions of the original screen, you are prompted for multiple values lists.</p> <p><b>*BLANKS</b> Search on a blank value.</p> <p><b>*ZEROS</b> Search for amounts equal to zero.</p> <p><b>*RANGE</b> Enter a range of values (example: 1 to 50). NOTE: The first value MUST be LESS than the second value.</p> <p><b>*ALL</b> Select all values.</p> <p>NOTE: If you leave this field blank, the default value is *ALL.</p>
Bracket Selection Ending	<p>A collection of open and closed brackets to group conditional configurator rules.</p> <p>For example, to define the condition (Seg 1 = A OR Seg 2 = B) AND Seg 3 = C, use the following brackets:</p> <p>(Seg 1 = A O Seg 2 = B) A Seg 3 = C</p>

Field	Explanation
Required or Optional	<p>Indicates whether a segment is required or optional in a configuration, or whether it must be calculated to specification when entering a sales order.</p> <p>Valid codes are:</p> <ul style="list-style-type: none"> <li>R Segment answer is required during sales order entry.</li> <li>O Segment answer is optional during sales order entry.</li> <li>C Segment is calculated during sales order entry. You define the calculation with assembly inclusion rules.</li> </ul> <p>..... <i>Form-specific information</i> .....</p> <p>For cross segment editing rules, this value determines whether the invalid configuration error message is hard or soft.</p> <p>Valid codes are:</p> <ul style="list-style-type: none"> <li>R Hard error message</li> <li>O Soft error message</li> </ul>
Configurator Then Selection Value	<p>Indicates a “then” logic relationship for configuration rules. You can enter a specific UDC value or one of the following values:</p> <ul style="list-style-type: none"> <li><b>*VALUES</b> Enter up to 45 values on a separate window. NOTE: When you specify *VALUES in different versions of the original screen, you are prompted for multiple values lists.</li> <li><b>*BLANKS</b> Search on a blank value.</li> <li><b>*ZEROS</b> Search for amounts equal to zero.</li> <li><b>*RANGE</b> Enter a range of values (example: 1 to 50). NOTE: The first value MUST be LESS than the second value.</li> <li><b>*ALL</b> Select all values.</li> </ul> <p>NOTE: If you leave this field blank, the default value is *ALL.</p>


### ► To set up values

---

On Cross Segment Editing

1. Complete the following field with \*VALUE:
  - Value

The system prompts you for the valid values for the rule you are entering.



2. On Value Selection, complete the following field:
  - Value

Field	Explanation
Selection value	<p>The data selection value. A special facility has been provided to allow selection of multiple specific values. By entering '*VALUES' in the selection field, a special display screen will be displayed allowing the entry of up to 45 specific values. If you specify '*VALUES' in multiple selections of the original display, you will be prompted for multiple values lists.</p> <p>Enter the value '*BLANKS' if you are searching on a blank value. You cannot leave the values field blank to search on blanks, it will default to '*ALL'. Enter the value '*ZEROS' when searching for amounts equal to zero.</p> <p>The '*RANGE' keyword will display a special display screen which will allow the entry of a range of values (i.e., from 1 to 50). The first value MUST be LESS than the second value. If it is equal or greater than, it will not work.</p> <p>If you want to select all values for a field, enter '*ALL'.</p>

## What You Should Know About

**Revising \*VALUE** To revise existing \*VALUE entries, place the cursor on \*VALUE and choose the Range and Values function.


### To set up ranges

---

On Cross Segment Editing Rules

1. Complete the following field with \*RANGE:
  - Value

The system prompts you for the range from and to values.



2. On Value Selection, complete the following fields:
  - From Range
  - To Range

Field	Explanation
Selection Values 01	The list of selection values associated with a data selection item in the Dream Writer. This list is generated by the use of the *VALUES keyword in data selection setup. Elements 1 and 2 are also used to contain the upper and lower value for the keyword *RANGE used by the data selection in the Dream Writer.
Selection Values 02	The list of selection values associated with a selection item in the Dream Writer. This list is generated by the use of the *VALUES keyword in data selection set-up. Elements 1 and 2 of this array are also used to contain the upper and lower value for the keyword *RANGE utilized by the data selection processing in the Dream Writer.

### What You Should Know About


#### Revising \*RANGE

To revise existing \*RANGE entries, place the cursor on \*RANGE and choose the Range and Values function.

► **To copy a rule**

On Cross Segment Editing

1. Access Rules Copy Window.



2. Locate the configured item from which you want to copy a rule.
3. Do one of the following:
  - To select the line, choose the Select Value option.
  - To select the complete rule, choose the Select Group option.

## What You Should Know About

### Calculated segment rules

Calculated segment values appear in cross-segment editing rule error messages.

### Separating rules

The system automatically separates rules with the line *Next Edit Group* after you enter all the rules.

### Multi-level configured items

You can reference upper level items in a cross-segment editing rule.

### **Setting up generic branch/plants**

You can define segments, rules, and configured items that are specific to a branch/plant specific or generic across all branch/plants.

A blank Branch/Plant field identifies a generic branch/plant.


If you don't use the generic branch plants, then segment, rule, and item information should be the same across branch/plants.

If you define generic branch/plants segments, you must also define generic cross-segment editing and assembly inclusion rules.

### **See Also**

- *Working with Error Messages (P4211)*

## **Setting Up Custom Error Messages**



From Configurator (G32) enter 29

From Configurator Setup (G3241) choose Cross Segment Editing


You can create custom messages that override the system messages for a cross-segment editing rule.

### **▶ To set up custom error messages**

---


On Cross Segment Editing

1. Complete the following field with Y:
  - Text
2. Choose the Custom Text Message option.



3. On Configurator Custom Messages, type the text for the error message.

## Reviewing Cross-Segment Editing Information



From Configurator (G32), enter 29


From Configurator Setup (G3241), choose Cross Segment Where Used

Review cross-segment editing information to help you maintain rules. For the item number and segment that you specify, review and work with all the cross-segment editing rules.

### ► **To review cross-segment editing information**

---

On Cross Segment Where Used



Complete the following fields:

- Branch Plant
- Item Number
- Segment Number

## See Also

- *Printing Reports (P32910)*



## Exercises

See the exercises for this chapter.

# Understand Derived Calculations

---

## About Derived Calculations

For an assembly inclusion rule, you can define derived calculations to determine:

- Quantity of a part to include on the work order or sales order
- Value of a calculated segment
- Run or machine hour multiplier for a routing
- Price multiplier

You can use the following functions within a derived calculation

- Algebraic formulas
- Segment references
- Trigonometric functions
- Substrings
- Concatenations
- External field references
- External program references
- Smart part calculations

### Algebraic Formulas

Use algebraic formulas to combine different operations with the following operators: + , - , \* , and /. You can imbed calculations by enclosing them in parentheses. You can imbed segment numbers in the formula to include segment values as part of the calculation.

For example, the following formula calculates the counter weight necessary so that the forklift will not tip over when its boom is extended to its tallest height with a full load:

**Derived Calculation**       $S10/(4*\text{COS}(2*S30*3.1416/360*2*3.1416))$

### Segment References

You can reference any segment within a formula. To reference a segment within the same configured item, enter S and the segment number. For example:

**S3**                                      Indicates segment three

To reference a segment from a different configured item, enter S, the segment number, and the configured item name. Enclose the item name within equal signs. For example:

**S3=Piston=**                              Indicates segment three of item Piston

When you reference another segment in a multi-level configured item, you can only reference upper levels.

## Trigonometric and Logarithmic Functions

You can use trigonometric or logarithmic functions independently or as part of a complex formula.

The following trigonometric functions are available:

<b>SIN(1.5)</b>	Indicates the sine of 1.5
<b>COS (S3)</b>	Indicates the cosine of segment three
<b>TAN(S3)</b>	Indicates the tangent of segment three
<b>ARC(S3)</b>	Indicates the arctangent of segment three

All of these values are expressed in radians.

The following logarithmic functions are available:

<b>LOG</b>	Indicates log to base 10.
<b>LN</b>	Indicates natural log.
<b>**</b>	Indicates an exponent. For example, 2**5 represents 2 to the fifth power.

### Substrings

You can use the SUBSTR (substring) function to include a portion of a larger string of characters in a formula.

To calculate a substring, you must reference the segment from which you want to take the substring, the starting position within the string where you want to begin referencing values, and the length of the string you want to reference. For example, if segment 10 is 400012 then:

**SUBSTR(S10,1,4)**

Indicates that the substring from segment 10 starts at the first position of the string and includes the next 4 positions. The substring value is 4000.

**SUBSTR(S10,5,2)**

Indicates that the substring from segment 10 starts at the fifth position of the string and includes the next 2 positions. The substring value is 12.

### Concatenations

You can use the CONCAT (concatenate) function to combine the values of two different segments. For example:

**CONCAT(S3,S4)**

Combines the values of segments 3 and 4. If the segment value of segment 3 is 1001 and the value of segment 4 is WH (white), the concatenated value is 1001WH.

## Referencing External Fields

You can select field values from the External Files Reference form to use in derived calculations. Choose a field from the following tables:

- F4101 – Item Master
- F4102 – Item Branch
- F41021 – Item Location
- F4105 – Cost Ledger
- F4106 – Base Price
- F0101 – Address Book Master
- F0301 – Customer Master
- F41002 – Unit of Measure Conversion
- F41092 – Supplemental Database
- F46011 – Item/Unit of Measure Profile

After you reference a field value, the information appears in the Derived Calculation field preceded by an ampersand (&). You can use the field independently or within a complex expression.

For rule types P, R, X and C, the system uses the component item number and branch from the rule to retrieve the appropriate tables.

The system uses the Address Book number to retrieve data from the Address Book or Billing Instructions tables.

When you reference a Supplemental Database field, you must also specify the data type. Enter the data type after the field as follows:

<b>&amp;T2AMTU(WD)</b>	Indicates an amount field on the item supplemental database table, and the WD data type.
------------------------	--

When you reference the Unit of Measure in Unit of Measure Conversion tables, you must specify the unit of measure in the same manner.

### Referencing External Programs

You can use an external program to define a calculation. Enter the name of the external program. You must also indicate EXTVAR in the Derived Calculations field. After the system runs the external program, it places the results in EXTVAR, a 30 character variable in the inclusion rule.

For P and R rules, the external program references the component number, component branch, and sold to number.

For C or X rules, the external program references the configured item number, branch/plant, and sold to number.

The external program can also access and use the values of previously entered segments sorted in user indexes. The system passes the following parameters to the external program are:

- Item number
- Branch/Plant
- DSKITP, a comprehensive data structure that contains many different values.
- EXTVAR

### Calculating Smart Parts

For P and Q rules, you can build smart part numbers using the segment values from sales order entry. The system calculates smart parts in a similar manner to derived calculations, however the resulting smart part is an alphanumeric string. You must define smart part numbers in the Item Master (F4101) and Branch/Plant (F4102) tables.

You can build a part number by using following functions:

- Segment referencing
- Substring
- Concatenation
- Literal text, for example the letter P in part number P165

Smart part formulas can define short, second or third part numbers. Smart parts use the part numbering symbol conventions defined in Branch/Plant Constants. For example, if the smart part formula uses the symbol to identify the third part number along with the third part number, the system would place the second part number on the sales order and work order detail line.

When you define a smart part, you can also use a derived calculation to determine the quantity of the smart part to use.

For example:

**'P'S4**

Indicates a smart part number P2000, when the value of segment 4 is 2000.



# Set Up Assembly Inclusion Rules

---

## Setting Up Assembly Inclusion Rules

You must set up assembly inclusion rules that process requested options and features from sales order entry into the specific components, operations, and calculated values that are necessary to build and price the configured item.

There are five types of assembly inclusion rules:

### **Component Part (P) Rules**

Define the component parts to include on the sales order and work order parts list. You also define multi-level configured items with these rules.

For example, if segment 10 equals 6000 and segment 30 is greater than or equal to 10, then use part F170, else use part F175.

### **Work Order Component Part (Q) Rules**

Define the components to include on the work order parts list. The Process Work Orders program attaches the parts list.

For example, if segment 10 equals standard, then include part R100 and part R105.

### **Pricing (X) Rules**

Define the price/cost adjustment. The system processes X rules independently based on the kit pricing method you have selected. You should not set up cost adjustments when using work order-generated line types.

For example, if segment 40 equals CUS, then adjust the price by \$650.00.

### **Routing (R) Rules**

Define the work order routing and routing operations. The Process Work Orders program attaches work order routings. You must first define the routings on Enter/Change Routing before you define routing rules.

For example, if segment 40 equals STD, then use the routing for standard paint, else use the routing for custom paint.

**Calculation (C) Rules** Define the mathematical calculation for a configured item's calculated segments. You must first define the segment as calculated on Configured Item Segments.

Setting up assembly inclusion rules consists of the following tasks:

- Defining assembly inclusion rules
- Locating assembly inclusion rules

### Logic Statements

For each assembly inclusion rule, you can define an “if/then/else” logic statement for many conditions. The following assembly inclusion rules illustrates:

If Segment 10 equals 6000, and segment 30 is greater than 10, then include part F170, else include part F175.

You can use the following conditions:

- If
- Then
- Else
- And
- Or

### Advanced Assembly Inclusion Rules

For an assembly inclusion rule, you can define advanced assembly inclusion rules to:

- Expand the derived calculation formula
- Define smart parts
- Reference external fields
- Reference external programs
- Reference a table

## Derived Calculations

For each rule type, you can define calculations for a specific segment to determine the following:

<b>Calculation (C) Rules</b>	The value for a calculated segment
<b>Routing (R) Rules</b>	Run or machine hours multiplier for a routing or routing step
<b>Pricing (X) Rules</b>	Price multiplier
<b>Component (P and Q) Rules</b>	Quantity multiplier (similar to quantity per assembly)

For each calculation, the following functions are available:

- Segment referencing
- Algebraic expressions
- Trigonometric functions
- Exponential/logarithmic functions
- A substring function to select a subset of values from a segment
- A concatenate function to combine values from two segments
- References to fields from other files
- Segment definition with a custom-written external program

You can define a derived calculation on either Assembly Inclusion Rules or Advanced Rules.

## Understanding Smart Parts

For quantity rules (P rules and Q rules), you can build “smart part” numbers from the segment values that you entered on the sales order. The simplest form of a smart part is that the answer to a segment question is a part number. The system calculates smart parts in a similar manner to derived calculation string-related operations.

## Referencing External Fields

As you define a derived calculation, you can include field values on External Files Reference. For example, a pricing assembly inclusion rule for FORKLIFT-A uses a field reference to retrieve a base price from the Base Price table (F4106).


## Referencing External Programs

You can reference an external custom program for special calculations. This is useful if the calculation requires several steps or requires more characters than available.

## Multi-Level Processing

If a configured item includes multiple levels, the system processes each component down the item hierarchy before processing across. This process determines the order in which segments appear during sales order entry.

For example, in the following configured item, forms appear during sales order entry in the order A, B, C, D, E:



Consider multi-level processing before you set up your rules, so that the system references segments for previously entered values. Use P type assembly inclusion rules to define your multi-level configured items. If you use configured items as components within multi-level configured items, ensure that the configured component items are unique.

## Referencing Table Names


You can use advanced rules to reference a table that returns calculated segment values, prices, and parts to the assembly inclusion rules.

**Referencing segments** For both Q and P rules, you can reference upper and lower level segments from assembly inclusion rules, tables and derived calculations.

### See Also

- *Working with Tables (P3281)*
- *Understand Derived Calculations (P3293)*

## Defining Assembly Inclusion Rules



From Configurator (G32) enter 29.

From Configurator Setup (G3241) choose Assembly Inclusion Rules.

Defining assembly inclusion rules consists of the following tasks:

- Defining unconditional rules
- Defining conditional rules
- Defining values
- Defining ranges
- Setting up advanced rules (optional)
- Copying rules (optional)

### ▶ **To define unconditional rules**

---

Before you define conditional rules, you can define unconditional rules to include parts, adjustments, calculated values, or routing steps regardless of the values in segment questions.

On Assembly Inclusion



1. Complete the following fields:
  - Branch/Plant
  - Rule Type
  - Configured Item
2. Complete the following field with an asterisk:
  - And/Or
3. Complete the following fields:
  - Item
  - Line Type

## ► To define conditional rules

On Assembly Inclusion

1. Complete the following fields:
  - Branch/Plant
  - Rule Type
  - Configured Item
  - If
  - Bracket
  - Segment
  - Relationship

- Values
  - Bracket
  - Then
  - Item
  - Operation Sequence
  - Line Type
2. Access the detail area.

The screenshot shows the 'Assembly Inclusion' window with the following fields and data:

- Branch/Plant: R30
- Rule Type: P
- Configured Item: FORKLIFT-R
- Item Description: Forklift, New Improved
- Skip to Rule No: (empty)

IF Condition		THEN Include			
R	( Seg Rel	Values	) Item	Oper Seq#	Ln Tg
#			8008		M
Seg Item			Seg Branch	Rule No	1
Quantity	1	ER Doc	Forklift Bacon	Sequence No	1
Description				Effective From	05/10/94
Comp Branch		R30	Issue Type Code I	Print Part	Thru 12/31/10
Derived Calc					
#			F165		S
Seg Item			Seg Branch	Rule No	1
Quantity	1	ER Doc	Counterweights	Sequence No	2
Description				Effective From	05/10/94
Comp Branch		R30	Issue Type Code I	Print Part	Thru 12/31/10
Derived Calc			(569/50)*1		

At the bottom of the window, there are several icons and a legend: F2=Range/Values F21=Print Opt 2=Routing 3=Copy Rule 4=Advanced Rules

3. Complete the following fields:
- Quantity
  - Effective From
  - Component Branch
  - Effective Thru
4. Complete the following optional fields:
- Segment Item
  - Segment Branch
  - Issue Type Code
  - Price Rollup
  - Derived Calculation

Field	Explanation
Branch/Plant	<p>A number that identifies a branch, plant, work center, or business unit.</p> <p>..... <i>Form-specific information</i> .....</p> <p>You can define a generic or blank branch/plant for assembly inclusion rules and then use the rules for all branch/plants.</p>
Rule Type	<p>Designates the type of included components:</p> <ul style="list-style-type: none"> <li>C Calculation</li> <li>P Part List</li> <li>Q Work Order Component</li> <li>R Route Sheet</li> <li>X Price/Cost Adjustment</li> </ul>
Configured Item	<p>A number that the system assigns to an item. It can be in short, long, or 3rd item number format.</p> <p>..... <i>Form-specific information</i> .....</p> <p>Header: The configured item number for which assembly inclusion rules are being defined.</p> <p>Detail: For P rules, this item is included in the parts list. For R rules, the routing for this item is copied.</p>
And/Or Selection	<p>A code that determines whether compound data selection logic is based on an A = AND condition or an O = OR condition.</p> <p>..... <i>Form-specific information</i> .....</p> <p>For configuration management, you can include parts, prices, costs, or routings with the configured item. Additional values include:</p> <ul style="list-style-type: none"> <li>I If</li> <li>E Else</li> <li>* Then</li> </ul> <p>For example:</p> <ul style="list-style-type: none"> <li>I Seg 1 = A</li> <li>* Part B</li> <li>E Part C</li> <li>E Part D</li> </ul> <p>If Seg 1 is A, include part B. If Seg 1 is not A, include part C and part D.</p>
Price	<p>The price charged for the unit of measure in the adjoining field. Use these fields, for example, if your primary unit of measure is EA (each), but you typically use a list price per box.</p>
Cost	<p>A user-defined cost the system uses based on information that you supply, which includes the name of the costing method and the method of calculation.</p>

Field	Explanation
Op Seq	<p>In routings, this number is used to sequence the fabrication or assembly steps in the manufacture of an item. You can track costs and charge time by operation.</p> <p>In bills of material, this number designates the routing step in the fabrication or assembly process that requires a specified component part. You define the operation sequence after you create the routing for the item. The Shop Floor Control system uses this field in the backflush/preflush by operation process.</p> <p>In engineering change orders, this number is used to sequence the assembly steps for the engineering change.</p> <p>Skip To fields allow you to enter an operation sequence that you want to begin the display of information.</p> <p>You can use decimals to add steps between existing steps. For example, use 12.5 to add a step between steps 12 and 13.</p> <p>..... <i>Form-specific information</i> .....</p> <p>For R rules, this value defines which routing step should be added to the configured item's work order routing.</p> <p>For P and Q rules, this value controls the consumption of material during backflush or super backflush transactions.</p>
Item Number – Unknown Format Entered	<p>The item number entered which can be in any of the three formats (short, long, or 3rd item number).</p> <p>..... <i>Form-specific information</i> .....</p> <p>The configured item number of the segment in the Assembly Inclusion Rule. Use this number to reference a previously selected segment.</p>
Price Roll Up Flag	<p>Determines whether the price/cost is rolled up into the parent item. The extended price/cost will be zero if the flag is set to roll up to the parent.</p> <p style="padding-left: 40px;">Y or 1 – Roll up price or cost to parent. N or 0 – Separate price/cost add-on.</p>

Field	Explanation
Effective From	<p>A date that indicates one of the following:</p> <ul style="list-style-type: none"> <li>• When a component part goes into effect on a bill of material</li> <li>• When a routing step goes into effect as a sequence on the routing for an item</li> <li>• When a rate schedule is in effect</li> </ul> <p>The default is the current system date. You can enter future effective dates so that the system plans for upcoming changes. Items that are no longer effective in the future can still be recorded and recognized in Product Costing, Shop Floor Control, and Capacity Requirements Planning. The Material Requirements Planning system determines valid components by effectivity dates, not by the bill of material revision level. Some forms display data based on the effectivity dates you enter.</p>
Thru	<p>A date that indicates one of the following:</p> <ul style="list-style-type: none"> <li>• When a component part is no longer in effect on a bill of material</li> <li>• When a routing step is no longer in effect as a sequence on the routing for an item</li> <li>• When a rate schedule is no longer active</li> </ul> <p>The default is December 31 of the default year defined in the Data Dictionary for Century Change Year. You can enter future effective dates so that the system plans for upcoming changes. Items that are no longer effective in the future can still be recorded and recognized in Product Costing, Shop Floor Control, and Capacity Requirements Planning. The Material Requirements Planning system determines valid components by effectivity dates, not by the bill of material revision level. Some forms display data based on the effectivity dates you enter.</p>
Comp Branch	<p>A secondary or higher level business unit. Sometimes used to reference a branch or plant with several departments or jobs subordinate to it.</p> <p style="margin-left: 40px;">Branch/Plant – (MMCU)  Dept A – (MCU)  Dept B – (MCU)  Job 123 – (MCU)</p>

Field	Explanation
Issue Type Code	<p>A code that defines how the system issues each component in the bill of material from stock. In shop floor control, it indicates how the system issues a part to a work order. Valid codes are:</p> <ul style="list-style-type: none"> <li>I Manual issue (default)</li> <li>F Floor stock (no issue)</li> <li>B Backflush (when part is reported as complete)</li> <li>P Preflush (when parts list is generated)</li> <li>U Super backflush (at pay-point operation)</li> <li>S Sub-contract item (send to supplier)</li> <li>Blank Shippable end item</li> </ul> <p>You can issue a component in more than one way within a specific branch/plant by using a different code on the bill of material and work order parts list. The bill of material code overrides the branch/plant value.</p>
Print Part	<p>This field will determine if the Configurator part should print on the sales order and work order. The flag will be used in the Pick Slip, Invoice Print, Bill of Lading, and Print Parts List.</p> <ul style="list-style-type: none"> <li>Y Print on sales and work order</li> <li>N Do not print on sales and work order</li> <li>2 Print on sales order only</li> <li>3 Print on work order only</li> </ul> <p>You can also use 1 for Y and 0 for N.</p>

Field	Explanation
Derived Calculation	<p>Defines an algebraic formula that calculates the quantity, price, hours or a value associated with a rule.</p> <p>For example:</p> <p>Segment References</p> <ul style="list-style-type: none"> <li>• S3 indicates segment 3.</li> <li>• S3=Piston= indicates segment 3 in item Piston.</li> </ul> <p>Trigonometric and Logarithmic Functions</p> <ul style="list-style-type: none"> <li>• SIN(20) indicates the sine of 20.</li> <li>• COS(S3) indicates the cosine of segment 3.</li> <li>• TAN(S4) indicates the tangent of segment 4.</li> <li>• ARC(S) indicates the arctangent of segment 3.</li> <li>• LOG indicates log to base 10.</li> <li>• LN indicates natural log.</li> <li>• 2**5 indicates an exponent, 2 to the fifth power.</li> </ul> <p>Substring</p> <ul style="list-style-type: none"> <li>• SUBSTR(S10,1,4) indicates that the substring from segment 10 starts at the first position of the string and includes the first 4 positions.</li> </ul> <p>Concatenations</p> <ul style="list-style-type: none"> <li>• CONCAT(S3,S4) combines the values of segments 3 and 4.</li> </ul> <p>External Fields</p> <ul style="list-style-type: none"> <li>• To specify external fields from external files. use &amp; followed by the field name. For example, &amp;T2AMTU(WD) indicates an amount field on the Item Supplemental Database table, and the WD data type.</li> </ul> <p>External Programs</p> <ul style="list-style-type: none"> <li>• To define an external program for the calculation, enter the name of the external program and EXTVAR in the Derived Calculations field.</li> </ul> <p>Smart Parts</p> <ul style="list-style-type: none"> <li>• PS4 indicates a smart part number P2000 when the value of segment 4 is 2000.</li> </ul>
Quantity – Standard Required Quantity	The number of units to which the system applies the transaction.

## What You Should Know About

### **Price rollup**

During sales order entry processing of pricing rules, the system compares the line type of the configured item on the sales order to “true” x rule line types. If the line types match, the price adjustment is reflected in the configured parent’s unit price. If the line types are different, the price rollup field is used to determine if the price adjustment is reflected in the parent’s unit price.

### **Revising lines**

You can use the insert line option and the delete line option to revise the assembly inclusion rules.

### **Assembly inclusion rule processing**

During sales order entry, the system processes each assembly inclusion rule independently by rule type from top to bottom in the following order:

- C rules
- Cross-segment editing rules
- P rules
- Q rules (if necessary)
- R rules (if necessary)
- X rules


## **To define values**

---

### On Assembly Inclusion

1. Complete the following field with \*VALUE:
  - Value

The system prompts you to work with \*VALUE entries on Value Selection.



2. On Value Selection, complete the following field:
  - Value

### What You Should Know About

#### **Revising \*VALUE**

To revise existing \*VALUE entries, place the cursor on \*VALUE and choose the Range/Values function.


#### **▶ To define ranges**

---

#### On Assembly Inclusion

1. Complete the following field with \*RANGE:
  - Value

The system prompts you for all new and changed rules containing a \*RANGE.



2. On Value Selection, complete the following fields:
  - From Range
  - To Range

## What You Should Know About

### Revising \*RANGE

To revise existing \*RANGE entries, place the cursor on \*RANGE and choose the Range/Values function.

### ► To set up advanced rules

---

On Assembly Inclusion Rules

1. Access Advanced Rule Functions.

[32931] - Advanced Rule Functions

Functions Tools Help

Derived Calc

Ext Program

Table Name

Smart Part \*\$50


Enter=Update F3=Exit w/o Update F10=Table Definition

2. On Advanced Rule Functions, complete one or more of the following fields:
  - Derived Calculation
  - External Program
  - Table Name
  - Smart Part

## ► To copy rules

On Assembly Inclusion

1. On a blank line, access Rules Copy Window.



2. On Rules Copy Window, locate the configured item from which you want to copy a rule.
3. Do one of the following:
  - To select a line, choose the Select Value option.
  - To select the complete rule, choose the Select Group option.

## Processing Options for Assembly Inclusion Rules

DEFAULTS:

1. Enter the default Rule Type. \_\_\_\_\_

COMPONENT BRANCH:

2. Enter a '1' to change the Component Branch (ADDITIONS ONLY) to that which is displayed at the top of the screen. \_\_\_\_\_

## Locating Assembly Inclusion Rules

You review assembly inclusion rule information to help you maintain these rules. You can determine the effect of component changes such as shortages and substitutions, and determine the effect of changes to valid segment values. For example, if a vendor discontinues a paint color, you can determine how many configurations will be affected.

Locating assembly inclusion rules consists of the following tasks:


- Locating component information
- Locating segment information

### See Also

- *Printing Reports (P32910)*

### ► To locate component information

---



From Configurator (G32) enter 29.

From Configurator Setup (G3241) choose Component Where Used


On Component Where Used

D	P	Configured Item	Branch	Rule No	Seq No	Ln Ty	Quantity Per	S
		FORKLIFT	R30	1	1	M	1	C
		FORKLIFT-R	R30	1	1	M	1	C

Complete the following fields:

- Branch Plant
- Rule Type
- Component Item

► **To locate segment information**



From Configurator (G32) enter 29.

From Configurator Setup (G3241) choose AIR Segment Where Used.

On AIR Segment Where Used

Ln	Seg	Rel	Value	Configured Item	Branch/Plant	Ln Ty
1	10	E0	6098	FORKLIFT-R	R30	3

Complete the following fields:

- Branch Plant
- Rule Type
- Item Number
- Segment Number



### Exercises

See the exercises for this chapter.



# Understand Tables

---

## About Tables

A table is a collection of data that you define for configured items. An assembly inclusion rule references a table. When the system processes rules during sales order entry and work order generation, it uses the table reference and table data to retrieve component parts and calculated values.



The tables used for matrix processing within the Configuration Management system are not User Defined Code tables or file tables.

You can define the following tables that correspond to the matching assembly inclusion rule types:


<b>Pricing table (Type X)</b>	Defines a price table that returns one numeric value.
<b>Part tables (Types P and Q)</b>	Define part tables that can return multiple alphanumeric values.
<b>Calculated value table (Type C)</b>	Defines a calculated segment table that can return numeric or alphanumeric values as defined on Configured Item Segments.

Setting up tables adds time to the setup process, but tables can dramatically reduce the number of assembly inclusion rules and their complexity, thus improving processing time.

Because a table might contain many segments and multiple return values, you must decide how the table information appears before you can review table information. Use a table key to control which portion of the table appears. You define a key with enough segment values so that table values appear in a column and row format. The information defined on Table Key controls which table values appear on Table Detail.

The key is a combination of segment answers that the system uses to access the table and return the associated values. You can define up to ten keys to determine the dimensions of the table.

## Table Key



On Table Keys, you can specify segment values in the following ways:

- Entering the specific value
- Choosing from available values (if table is already defined)
- Entering an asterisk at every segment to select from available segment values in the sequence that you define.

On Table Keys, you can set up several types of locks that control how table values appear:

- Exact lock – you define all segment values
- Column lock – you define all segment values but the last
- Table lock – you define all segment values but the last two (this is only available for tables that return single values)



The amount of table information that subsequently appears on Table Detail depends on two factors:

- The number of segments defined on Table Definition
- The number of return values you defined on Table Definition

The following examples illustrate some of the different methods for working with table values.

### Example: Multiple Segments, Exact Lock



On Table Keys, define the values for each segment. A single row that represents the locked value for the last segment appears on Table Detail. The columns represent the multiple values that you defined for the table.



### Example: Multiple Segments, Column Lock

On Table Keys, define all segment values except for the last segment. Rows which represent values for the last segment, and columns which represent multiple table values appear on Table Values.

You can scroll to the left and right, and page up and down to review the table values.



# Set Up Tables

---

## About Tables

A configured rules table is a collection of data that you define for a configured item. An assembly inclusion rule references a table. When the system processes rules during sales order entry and work order generation, it uses the table reference and table data to retrieve component parts, calculated values, or price adjustments.

The tables used for matrix processing within the Configuration Management system are not User Defined Code tables or file tables.

You can define the following tables that correspond to the matching assembly inclusion rule types:

<b>Pricing table (Type X)</b>	Defines a price table that returns one numeric value.
<b>Part tables (Types P and Q)</b>	Define part tables that can return multiple alphanumeric values.
<b>Calculated value table (Type C)</b>	Defines a calculated segment table that can return numeric or alphanumeric values as defined on Configured Item Segments.

Setting up tables adds time to the setup process. However tables can dramatically reduce the number of assembly inclusion rules and their complexity, thus improving processing time.

Because a table might contain many segments and values, you must decide how the table information appears before you can review table information. As you work with table information, you can set a processing option for copying rows of data to speed data entry.


## Setting Up Tables

Assembly inclusion rules reference tables which you define to return calculated segment values, prices and component parts. The table type should be the same as the assembly inclusion rule type that accesses it.

Setting up tables consists of the following tasks:

- Setting up table dimensions
- Setting up configured item cross-reference
- Setting up table values
- Linking a table to an assembly inclusion rule
- Printing table information

### Setting Up Table Dimensions



From Configurator (G32) enter 29.

From Configurator Setup (G3241) choose Table Definition.

For each table, you must define the:


- Table name in user defined code table 32/TN
- Table dimensions, including:
  - Table type
  - Number of segments that specify the key to the table
  - Number of values it will return

You define table names on a user defined code table. However, the Configuration Management data table is not a user defined code table.


#### **▶ To set up table dimensions**

---

On Table Definition



1. Access User Defined Code Revisions.



2. On User Defined Code Revisions, complete the following fields:
  - Character Code
  - Description
3. Access Table Definition.
4. On Table Definition, complete the following fields:
  - Branch/Plant

- Table Type
- Rules Table Name
- Table Description
- Number of Segments
- Number of Table Values

Field	Explanation
Table Type	Designates the type of rule table. Valid values are: C      Calculated values P      Part list (on sales order and work order) Q      Work order component (on work order only) X      Price/Cost adjustment
Rules Table Name	<p>You must define table names in user defined code table 32/TN. A rule table is a collection of data that is set up to minimize the number of assembly inclusion rules you need for a configured item. A rule table can be accessed by 1 to 10 keys and can return up to 99 values. When you reference a rule table in an Assembly Inclusion Rule, the system uses the rule keys to read the rule table and retrieve the values associated with the table</p> <p>For example, if you defined segment 10 to be the color of an item, you could set the table to retrieve item Red Component if the customer enters Red for segment 10. In this example, the table would be:</p> <pre>Item Color = Value Red = RED COMPONENT</pre> <p>The table would read: If the color segment value = red, then use item number RED COMPONENT on the configured item sales order and work order parts list.</p>
Number of Segments	Indicates how many keys are used to access the table. Key values must be on the current level or a previous level of the configured item.
Number of Table Values	The Number of Values tells the system how many values should be returned from the rule table when a match is found on the table keys. If you enter more than one return value for a C (calculated) rule, you must indicate the segment numbers to return the values to.

### What You Should Know About

#### **Deleting table definitions and table values**

You can delete a table value at the intersection of the row and column. If you delete a table definition, the system also removes the related table values.

## Processing Options for Table Definition

RULE TABLE DEFAULT VALUES:

1. Rule Table Type (Optional) \_\_\_\_\_

## Setting Up Configured Item Cross-Reference



From Configurator (G32) enter 29.

From Configurator Setup (G3241) choose Configured Item Cross Reference.

After you define a table, you must associate it with a configured item and define the specific segments that access it. To create a cross-reference, the number of segments that you specify must equal the number of segments that you defined for the table.

You can also specify a segment that accesses a different configuration level.

Multiple configured items can reference a single table, and a single configured item can reference multiple tables.

### ▶ To set up a configured item cross-reference

On Configured Item Cross Reference

Seg	Seg	Description	Segment Item	Segment Branch
1	20	Lift Rating		
2	20	Power Type		

Complete the following fields:

- Branch/Plant
- Table Type
- Table Name
- Configured Item
- Segment
- Segment Item
- Segment Branch

### What You Should Know About

**Generic cross-references**

You can enter an item \*ALL to define a generic cross-reference for all configured items. If you use \*ALL, you must use the same segment numbers across all configured items. This defines keys for all configured items that access the table.

**Using multiple return values with a calculation table**


When you define a calculation table with multiple return values, you must specify on Value Definition the segment numbers that will be populated with table values.

### Processing Options for Configured Item Cross Reference

RULE TABLE DEFAULT VALUES:

1. Rule Table Type (Optional) \_\_\_\_\_

### Setting Up Table Values



From Configurator (G32) enter 29.

From Configurator Setup (G3241) choose Table Keys.

To enter table values quickly, consider setting a processing option to enable row copying.

**▶ To set up table values**

---

On Table Keys


Branch/Plant R30  
Table Type P

Table Name LIFT Lift Rate-Power Type


Segment Description	Value
Lift Rating	4000
Power Type	GRS

F10=Table Values F24=More

1. Complete the following fields:
  - Branch/Plant
  - Table Type
  - Table Name
2. Complete the following field for the first segment:
  - Value
3. Complete the following field for the last segment:
  - Value
4. Access Table Values.



5. On Table Values, complete the following field for each segment:
  - Value
6. Access the detail area.



7. Complete the following fields:
  - Quantity
  - Unit of Measure

Field	Explanation
Table	The Table Segment Value is a value used as a key to a table.
Rules Table Value	The Rules Table Value is the value that is returned from a rules table.
Item Number – Unknown Format Entered	The item number entered which can be in any of the three formats (short, long, or 3rd item number).
Amount	The actual amount. Debits are always entered as plus (+), and credits are entered as minus (-). You may enter decimals, dollar signs, and commas. The amount field will be examined and any non-significant symbols will be removed. Minus signs must be entered as a trailing figure. For example, the amount 5,000.01- would be interpreted as a credit of 5000.01.

## See Also


- *Understand Tables*

## Processing Options for Table Keys

RULE TABLE DEFAULT VALUES:

1. Rule Table Type (Optional)

## Linking a Table to an Assembly Inclusion Rule




From Configurator (G32) enter 29.

From Configurator Setup (G3241) choose Assembly Inclusion Rules.


After you have defined a table and the segment that accesses its values, you must link the table to the assembly inclusion rule for that segment.

### ▶ **To link a table to an assembly inclusion rule**

On Assembly Inclusion



1. Access Advanced Rule Functions for the segment that you want to link to a table.



2. On Advanced Rule Functions, complete the following field:
  - Table Name

## Printing Table Information



From Configurator (G32) enter 29.

From Configurator Setup (G3241) choose Table Report.

Print the Table Report to review the table segments and values for the table name and table type that you specify.

Power Type		Value	Value
BATTERY	F105	1 EA	F130 Qty. . 1 EA
GAS	F105	1 EA	F120 Qty. . 1 EA
PROPANE	F105	1 EA	F125 Qty. . 1 EA
TRANS	F105	1 EA	F185 Qty. . 1 EA
WARP	F105	1 EA	F180 Qty. . 1 EA



### Exercises

See the exercises for this chapter.



# Print Reports

---

## Printing Reports

You can review the following information about a configured item with available Configuration Management reports:

- Where segments are used in configured items
- Assembly inclusion rules
- Cross-segment editing rules

Use these reports to analyze demand for options and features and to maintain rules.

Printing reports consists of the following tasks:

- Printing segment information
- Printing cross-segment editing rules
- Printing assembly inclusion rules



## Printing Cross-Segment Editing Rules



From Configurator (G32) enter 29.

From Configurator Setup (G3241) choose Cross Segment Editing.

Print this report to review all cross-segment editing rules for the configured item that you specify.

32492		J.D. Edwards & Company				Page - 8			
		Segment Editing Rules Print				Date - 4/16/96			
Product Family . FORKLIFT-A						Branch . M30			
Forklift, New Improved									
If Parent Segment Rules State:				Edit So Segment Must Be:					
Cond	( Seg	Segment Description	Rel	Value	) Seg	Segment Description	Req Rel	Value	Text
----	----	-----	---	-----	----	-----	---	-----	----
If	( 10	Lift Rating	EQ	6000	) 20	Power Type	R EQ	*VALUE	Y
							Rule No	1	
								Seq No	1
								GAS	
								PROPANE	
								TRANS	
								WARP	
		A 6000 LB capacity Forklift requires a gas or propane engine.							
		Next Edit Group. . . . .							
If	( 10	Lift Rating	LE	4000			Rule No	2	
								Seq No	1
Or	20	Power Type	EQ	BATTERY	) 30	Boom Height	R LE	10	Y
								Seq No	2
Else					30	Boom Height	R LE	12	Y
								Seq No	3
		Next Edit Group. . . . .							
If	( 10	Lift Rating	EQ	6000			Rule No	3	
								Seq No	1
And	20	Power Type	EQ	PROPANE	) 50	Propane Tank	R EQ	50	2
								Seq No	
		Next Edit Group. . . . .							
If	20	Power Type	NE	PROPANE	50	Propane Tank	O EQ	*BLANK	Y
							Rule No	4	
								Seq No	1

## Printing Assembly Inclusion Rules



From Configurator (G32) enter 29.

From Configurator Setup (G3241) choose Assembly Inclusion Rule Report.

Print this report to review all the assembly inclusion rules for the configured item that you specify.

32493		J.D. Edwards & Company Assembly Inclusion Rules Parts List				Page	-	12	
						Date	-	4/16/96	
Product Family . FORKLIFT-A Forklift, New Improved						Branch.		M30	
						Configurator Rul		P	
IF Condition:		THEN Include:							
Cond	(	Seg	Segment Description	Rel	Value	)	Component Item Number	Description	Ln
Use							BOOM Rule No 1	Forklift Boom Seq No 1	W
				Qty	1 EA		F165 Rule No 1	Counterweights Seq No 2	S
			DC (S60/50)+1	Qty	1 EA				
Use							Rule No 1	Seq No 3	S
Use							Rule No 1	Seq No 4	S
					Next Edit Group . . . . .				
If			10 Lift Rating		EQ 6000		Rule No 2	Seq No 1	S
And			30 Boom Height		GE 10		Rule No 2	Seq No 2	S
Use							F170 Rule No 2	Pneumatic Tire Seq No 3	S
				Qty	4 EA		F175 Rule No 2	Hard Rubber Tire Seq No 4	S
Else				Qty	4 EA				
					Next Edit Group . . . . .				
If			40 Paint		EQ STD		Rule No 3	Seq No 1	S
Use							F150 Rule No 3	Yellow Paint Seq No 2	S
				Qty	1 EA				
					Next Edit Group . . . . .				
If			30 Boom Height		EQ 8		Rule No 6	Seq No 1	S
Use							F135 Rule No 6	8 Ft Boom Seq No 2	S
				Qty	1 EA				
					Next Edit Group . . . . .				
If			30 Boom Height		EQ 10		Rule No 7	Seq No 1	S
Use							F140 Rule No 7	10 Ft Boom Seq No 2	S
				Qty	1 EA				
					Next Edit Group . . . . .				
If			30 Boom Height		EQ 12		Rule No 8	Seq No 1	S
Use							F145 Rule No 8	12 Ft Boom Seq No 2	S
				Qty	1 EA				

# Sales Orders





# Configured Item Sales Orders

## Objectives

- To enter a sales order for a configured item

## About Sales Orders

After you have set up the segments, cross-segment editing rules, and assembly inclusion rules for a configured item, you can enter a sales order for the configured item.

When you enter a sales order for a configured item, the Configuration Management system automatically prompts you to enter values for the segments of that configured item. You set a processing option to select from the following sales order entry modes:

- Assisted mode
- Assisted prompt mode
- Text mode

The system edits each segment value against user defined code tables, ranges and numeric specifications. The Sales Order Entry program also processes cross-segment editing rules to validate feature and option compatibility. If there are no errors, the system processes the segment values according to the assembly inclusion rules.

## See Also

- *Working with Header Information (P4211)* in the *Sales Order Management Guide*
- *Working with Detail Information (P4211)* in the *Sales Order Management Guide*





# Work with Configured Item Sales Orders

---

## Working with Configured Item Sales Orders

You can enter a sales order for a configured item using one of the following methods:

<b>Text mode</b>	You can enter the segments as a string of characters separated by the segment delimiter. While using text mode, you can access both assisted prompt mode and assisted mode.
<b>Assisted mode</b>	All of the segments appear on a form with default values for each. You can select other values or accept the defaults.
<b>Assisted prompt mode</b>	The segments appear on one form and the choices for each segment appear on another. After you select values for all the segments, your choices appear on the first form. If you enter a multi-level configured item, the forms appear for each lower level item.


Working with configured item sales orders consists of the following tasks:

- Entering a sales order in text mode
- Entering a sales order in assisted mode
- Entering a sales order in assisted prompt mode
- Working with error messages
- Reviewing configured text
- Revising a sales order for a configured item
- Converting sales quotes for a configured item

## Before You Begin

- Set the processing option for the work order line type to create work orders or define the W line type in each configured item's branch/plant record. If you leave the processing option blank, the system supplies the line type from the branch/plant.
- Verify that you have set the processing option to the appropriate sales order entry mode.

## Entering a Sales Order in Text Mode



From Manufacturing Systems (G3) choose Configurator Operations.

From Configurator (G32) choose Enter/Change Sales Order.

After you have defined the sales order header with customer information, enter the configured item sales order in the sales order detail.

Entering a sales order in text mode consists of the following tasks:

- Entering item and customer information
- Entering a previously ordered configured item (optional)

### ► To enter item and customer information

---

On Sales Order Entry

Functions Options Tools Help

Mode (F)  Base Co Currency Code Branch/Plant R30  
Exchange Rate Order Date  
Cancel Date  
Order Number 80

Sold To 1801  
Ship To 1801  
Requested  
Customer PO

Detail By/Plt Skip To Line

Quantity	Item	U#	Unit Price	Extended Price	L1	U
1	F09LIFT-R	EA			M	U
					M	U
					M	U
					M	U
					M	U
					M	U
					M	U

F6=Summary F15=SO Header F24=More Keys Opt 1=Detail 2=Text 3=Del

1. Complete the following required fields:
  - Sold To
  - Branch/Plant
  - Quantity
2. Complete the following field with a configured item:
  - Item

The ATO Specification Text Format form appears.

[32941] - ATO Specification Text Format

Functions Tools Help

✓ X

Forklift, New Improved

Enter Segment Values Separator = /


6000/GAS/10/STD/13285.16

F5=Assisted Mode F6=Prompt Mode F8=History F24=More Keys

3. On ATO Specification Format, complete the following field:
  - Enter Segment Values

▶ **To enter a previously ordered configured item**

1. On ATO Specification Text Format, choose the Configured String History function.



2. On Configured String History, choose a configured string.
3. Revise the string as necessary and press Enter.

Field	Explanation
Sold To	A number that identifies an entry in the Address Book system. Use this number to identify employees, applicants, participants, customers, suppliers, tenants, and any other Address Book members.
Branch/Plant	A number that identifies a branch, plant, work center, or business unit.
Quantity	The quantity of units affected by this transaction.
Item	A number that the system assigns to an item. It can be in short, long, or 3rd item number format.
ATO Coded Specification Text Format Entr	This window will allow you to enter specific values for the segments making up a configured item. Segment values are separated by a special character, called the segment delimiter.

## Entering a Sales Order in Assisted Mode



From Manufacturing Systems (G3) choose Configurator Operations.

From Configurator (G32) choose Enter/Change Sales Order.

Entering a sales order in assisted mode consists of the following tasks:

- Entering item and customer information
- Entering a previously ordered configured item (optional)

► **To enter item and customer information**

On Sales Order Entry

The screenshot shows the SAP 'Enter/Change Sales Order' dialog box. The window title is '[42111] - Enter/Change Sales Order'. The interface includes a menu bar with 'Functions', 'Options', 'Locks', and 'Help'. Below the menu bar are several input fields and checkboxes:


- Mode (F) with a checkbox for 'Base Co'.
- Exchange Rate, Currency Code, Branch/Plant (F00), Order Date, Cancel Date, and Order Number (00).
- Sold To (1001), Ship To (1001), Requested, and Customer PO.
- Detail By/Pt and Skip To Line.

Below these fields is a table with the following columns: Quantity, Item, UM, Unit Price, Extended Price, and LT. The first row contains the value '1' in the Quantity column and 'F099LIFT-R' in the Item column. The UM column contains 'ER'. The Unit Price, Extended Price, and LT columns are empty. The table is followed by a vertical column of 'M' characters.

The footer of the dialog box contains the following text: 'F6=Summary F15=SO Header F24=More Keys Opt. 1=Detail 2=Text 3=Del'.


1. Complete the following required fields:
  - Sold To
  - Branch/Plant
  - Quantity
2. Complete the following field with a configured item:
  - Item

The Configured Item Specifications form displays.



3. Do one of the following:

- To accept the default values, press Enter.
- To select a segment value, access Segment Values Selection for a specific segment and select a value.



4. Repeat step 3 for the remaining lower level configured items.

► **To enter a previously ordered configured item**

1. From Configured Item Specifications, choose the Configured String History function.

Forklift, New Improved	Req Date
4000/GAS/10/STD//1,00	17.07.97
4000/GAS/10/STD//1,00	17.07.97
4000/GAS/10/STD//1,00	17.07.97

2. On Configured String History, choose a configured string.
3. Revise the string as necessary and press Enter.

## Entering a Sales Order in Assisted Prompt Mode



From Manufacturing Systems (G3) choose Configurator Operations.

From Configurator (G32) choose Enter/Change Sales Order.

Entering a sales order in assisted prompt mode consists of the following tasks:

- Entering item and customer information
- Entering a previously ordered configured item (optional)

► **To enter item and customer information**

On Enter/Change Sales Order

1. Complete the following required fields:

- Sold To
- Branch/Plant
- Quantity
- Item

The system prompts you to enter segment values by displaying a series of Segment Value Selection forms.

2. On Segment Value Selection, do one of the following:
  - Select a value from the list
  - Press Enter to accept the default value
3. Repeat step 2 for the remaining segments and lower level items.
4. To process the sales order, press Enter.
5. On Sales Order Entry, locate the sales order to display the individual line items.

The screenshot shows a window titled "[42111] - Enter/Change Sales Order". It contains various fields for order information and a table of line items.

Fields include:

- Mode (F):  Base Co
- USD Currency Code: USD
- Exchange Rate: [ ]
- Branch/Plant: 830
- Order Date: 17.07.97
- Cancel Date: [ ]
- Order Number: 112015 00
- Sold To: 1001 Edwards, J.O. &
- Ship To: 1001 Edwards, J.O. & Resales P.O.
- Requested: 17.07.97
- Customer PO: [ ]
- Detail By/Plt: 830
- Amount: 48.500,00
- Skip To Line: [ ]


Table of Line Items:

Quantity	Item	UR	Unit Price	Extended Price	LT	0
1	830S3FT-R	ER	48.500,0000	48.500,00	M	
					M	
					M	
					M	
					M	
					M	
					M	
					M	
					M	
					M	

Footer: F6=Summary F15=SO Header F24=More Keys Opt 1=Detail 2=Text 9=Del

► **To enter a previously ordered configured item**

1. Access Configured String History.



2. On Configured String History, choose configured string.
3. Revise the string as necessary and press Enter.

## What You Should Know About

### Vocabulary Overrides

Vocabulary overrides enable you to change the text on forms and reports. On the Configured Item Specification form (V3294), you can use vocabulary overrides to change constants defined for rule processing components including variable name, string delimiter, and field name identifier.

See *Working with Vocabulary Overrides* in the *Common Foundation Guide*.

### **Interbranch sales**

You can enter a configured item sales order to fill demand from a warehouse other than from the one where the order is placed. However the following functions are not supported:

- Pricing (X) rules for interbranch sales
- Transfer orders for configured items

Interbranch orders allow a branch to receive the order but supply the item directly from another branch. These orders can support markups between the branches, without inventory passing through the branch that received the order. The system does not support interbranch sales orders for configured items or pricing (X) rules.

See *Working With Detail Information* in the *Sales Order Management Guide*.

### **Preference profiles**

Configuration Management supports most preference profiles. Preference profiles help you automate the sales order entry process. Use a preference profile to define information that is consistent for a customer, customer group, configured item, or configured item group. Preference profiles are not supported for multi-branch commitments.

See *Working With Preferences* in the *Sales Order Management Guide*.

### **Multi-currency**

Pricing (X) rules are applied to foreign currency sales orders. The system processes price adjustments as a base currency amount and converts the amount to a different currency amount if necessary.

### **Commitments**

Soft commitments are added for a configured parent item with associated work orders. Component parts related to the configured parent are committed by the Process Work Orders program.

### **Trade discounts**

The Sales Order Management system does not support trade discounts for configured items.

### **Additional order processing**

For configured items, the Sales Order Management system does not support the following additional order processing:

- Credit orders
- Blanket orders
- Transfer orders
- Drop ship orders

### **Weight calculation**


If you have defined a conversion factor for primary UOM to weight UOM in the Item Master, then the Sales Order Entry program calculates the weight of the component parts to determine the parent weight. This calculation affects the following processes in your business flow:

- Shipping manifest requirements
- Freight charge calculations
- Advanced pricing requirements

Base weight conversion to which component weights will be added must be defined at the parent configured item level. In addition, item conversions to the parent weight UOM must be defined for each component. If no item conversion is found, the program looks to the Standard UOM Conversion table.

Components of a parent configured item that are also Stocking Type C items are included in the weight rollup to the parent.

## Working with Error Messages



From Manufacturing Systems (G3) choose Configurator Operations

From Configurator (G32) choose Enter/Change Sales Order.

During sales order entry, the system checks the values that you enter against the cross-segment editing rules and configured item segments. The system verifies that you have not entered any values that violate the editing rules. If a segment value violates an editing rule, either a hard or a soft error message appears.


Working with error messages consists of the following tasks:

- Working with hard error messages
- Working with soft error messages

### **▶ To work with hard error messages**

---


On Configurator Rules



1. Press F3 to return to Configured Item Specifications.
2. Select a different segment value.

► **To work with soft error messages**

On Configurator Rules




1. Do one of the following:

- To change the segment value, return to Configured Item Specifications and select a different segment value.
- To override the error message, choose the Accept Optional Message function.

### See Also

- *Cross Segment Editing Rules (P3292)*

## Reviewing Configured Text



From Manufacturing Systems (G3) choose Configurator Operations

From Configurator (G32) choose Enter/Change Sales Order.

You can review the configured text that you defined on Configured Item Segments. Configured text can include:


- Configured parent item's part number
- Segment number
- Segment description
- Segment value
- Associated user defined code table value description

### ▶ **To review configured text**

---

On Sales Order Entry

1. Locate the sales order for the configured item.
2. Access the Associated Text form.



### See Also

- For more information about working with associated text, see *Working With Associated Text (V401)* in the *Sales Order Management Guide*.

## Revising a Sales Order for a Configured Item



From Manufacturing Systems (G3) choose Configurator Operations

From Configurator (G32) choose Enter/Change Sales Order.

After you have entered a sales order, you can change the following information:

<b>Quantity</b>	Changes are reflected in the sales order and work order.
<b>Segment value</b>	Changes are reflected in the sales order and the work order.
<b>Pick date</b>	The system recalculates work order start dates based on leadtimes.

If you change the sales order after work has been started on the associated work order, the work order status will change, but the parts list and routing will not be affected. You can use constants to define the status beyond which changes will no longer affect the related work order. If the work order status is greater than

or equal to the value set on Configurator Constants, the system will not reflect the changes on the work order.



Configuration Management supports multi-level back scheduling when you change a sales order's pick date.

## ► To revise the sales order

On Sales Order Entry

Quantity	Item	UN	Unit Price	Extended Price	LT	0
1	FORKLIFT-A	FO			M	

1. Locate the sales order for the configured item.
2. Choose the Configured Item Change Processing option.

Item Number	Item Description
FORKLIFT-A	Forklift, New Improved
BOOM	Forklift Boom
FORK	Forklift Fork

3. On Multi-Level Product Selection, choose the item that you need to revise.

4. Access Configured Item Specifications.

5. On Configured Item Specifications, change the segment value and press Enter.

The Sales Order Entry form displays the changes.

## What You Should Know About

- Revising a sales order** You can also revise a sales order by entering an asterisk in the Quantity field.

## See Also

- *Setting up Constants (P3209)*

## Converting Sales Quotes for Configured Items



From Manufacturing Systems (G3) choose Configurator Operations

From Configurator (G32) choose Enter/Change Sales Quote.

You can enter a sales quote for a configured item and later convert the sales quote into a sales order.

Sales quotes are controlled by two Configuration Management constants. You must:

- Specify the type of sales quote to use to prevent work orders from being generated for quotes.
- Set up quote costing based on manufacturing net added costing.

You enter a sales quote the same way as you enter a sales order, except that the document type is automatically set for sales quotes.

### Before You Begin

- Set the Configurator Constants for sales quotes

### ► To convert a sales quote into a sales order

---

On Enter/Change Sales Quote

The screenshot shows the SAP 'Enter/Change Sales Quote' window. The title bar reads '[42111] - Enter/Change Sales Quote'. The menu bar includes 'Functions', 'Options', 'Locks', and 'Help'. The window contains several input fields: 'Mode (F)' with a radio button for 'Base Co', 'USD Currency Code' set to 'USD', 'Branch/Plant' set to '800', 'Order Date' set to '07/18/97', 'Exchange Rate', 'Cancel Date', 'Order Number' set to '360 SQ', 'Sold To' and 'Ship To' both set to '1001 Edwards, J.O. & Associates, P.O.', 'Requested' set to '07/18/97', 'Customer PO', 'Detail By/Pft' set to 'R30', 'Amount', and 'Skip To Line'. Below these fields is a table with the following data:

Quantity	Item	UN	Unit Price	Extended Price	L1	0
1	88853FT-R	EA	.0000		M	

At the bottom of the window, there is a status bar with the text: 'F6=Summary F15=SO Header F24=More Keys Opt 1=Detail 2=Text 3=Del'.

1. Locate the sales quote.
2. Choose the Create/Duplicate a Sales order function.
3. Process the sales order.

### See Also

- *Setting up Constants (P3209)*



**Exercises**

See the exercises for this chapter.

**Processing Options for Sales Order Entry – Detail**

SALES ORDER DEFAULT VALUES:

- 1. Document Type (Required) \_\_\_\_\_
- 2. Line Type (Optional) \_\_\_\_\_
- 3. Beginning Status (Optional) \_\_\_\_\_
- 4. Override Next Status (Optional) \_\_\_\_\_
- 5. Unit of Measure (Optional) \_\_\_\_\_
- 6. Line Number Increment (Optional) \_\_\_\_\_
- 7. Reason Code (Optional) \_\_\_\_\_

UNIT OF MEASURE DEFAULT VALUES:

- 8. Enter '1' to use the Pricing UOM as the default Transaction UOM. If left blank, the Primary UOM will be used instead. \_\_\_\_\_

WORK ORDER DREAM WRITER VERSIONS:

- Enter the version for each program.  
If left blank, ZJDE0001 will be used:
- 9. Work Order Entry (P48013) \_\_\_\_\_
  - 10. WO Server for Sale Order (X4201WO) \_\_\_\_\_

ORDER DUPLICATION DEFAULT VALUES:

- 11. Document Type \_\_\_\_\_
- 12. Beginning Status \_\_\_\_\_
- 13. Enter text duplication selection \_\_\_\_\_  
 '1' to copy line text  
 '2' to copy line and order text  
 '3' to copy order text

ADDRESS BOOK DEFAULT VALUES:

- 14. Enter a '1' to default the branch from the Address Book. If left Blank, it will default from the user default location. \_\_\_\_\_

DOWNLOAD HEADER INFORMATION:

- 15. Enter '1' to automatically load header values to the detail lines after a change. If left blank, it must be done manually. \_\_\_\_\_

PROMPTING CONTROL:

- 16. Enter the Screen Format: \_\_\_\_\_  
 1 = Quantity, Item, Price  
 2 = Quantity, Item, Description  
 3 = Item, Quantity, Price  
 4 = ECS format  
 5 = Aggregates format  
 (If left blank, format 1 is used.)

- Enter a '1' to:
- 17. Display Headings first. \_\_\_\_\_
- 18. Be prompted to accept the order. \_\_\_\_\_

NOTE: Two-cycle order entry is not recommended for configured items.

- 19. Allow the addition of a Customer \_\_\_\_\_

## Configuration Management

---

- Master record, if not set up.
20. Load Online Invoice information before the order is accepted. \_\_\_\_\_
21. Enter which Item Search screen is to be used to return items: \_\_\_\_\_
- 1 = Item Search window allowing the return of multiple items
- 2 = Full Item Search screen with Query capabilities
- (If left blank, the Item Search window allowing the return of a single item will be used.)
- ORDER HOLD CODES:
22. Customer Credit Checking \_\_\_\_\_
23. Order Margin Checking \_\_\_\_\_
24. Order Line Margin Checking \_\_\_\_\_
25. Order Minimum Value Checking \_\_\_\_\_
26. Order Maximum Value Checking \_\_\_\_\_
27. Partial Order Hold \_\_\_\_\_
28. Product Allocation Hold \_\_\_\_\_
- LINE CONTROL STATUS:
29. Enter the next status code beyond which a detail line cannot be changed. If left blank, no restriction will be put on the changing of a line. \_\_\_\_\_
- FIELD DISPLAY CONTROL:
- Enter '1' to protect or '2' to suppress:
30. Cost Fields \_\_\_\_\_
31. Price Fields \_\_\_\_\_
- Enter '1' to protect the following:
32. Status Codes \_\_\_\_\_
33. Price adjustment driver fields \_\_\_\_\_
34. Sold To field on the header \_\_\_\_\_
- Enter a '1' to suppress the following:
35. Closed Detail Lines \_\_\_\_\_
36. Credit Card Information \_\_\_\_\_
37. Freight and Carrier Information \_\_\_\_\_
38. Commission Information \_\_\_\_\_
- CREDIT ORDER PROCESSING:
39. Enter the status code to select when retrieving credit orders. \_\_\_\_\_
40. Enter '1' if the previous status is the last status. If left blank it will be the Next Status. \_\_\_\_\_
- CROSS REFERENCE INFORMATION:
41. Enter the Cross Reference Type for:
- Substitute Items \_\_\_\_\_
  - Associated Items \_\_\_\_\_
  - Replacement Items \_\_\_\_\_
42. Enter '1' to use the substitute item's Unit Price. If left blank, the original item's price will be used to order the substitutes. \_\_\_\_\_
- KIT PROCESSING:
43. Enter '1' to suppress Kit \_\_\_\_\_

- Component lines.
- 44. Enter the version of Kit Inquiry to call. If left blank, version ZJDE0001 will be called. \_\_\_\_\_
  - 45. Enter '1' to suppress availability information in the Kit Window. \_\_\_\_\_

AVAILABILITY CHECKING:

- 46. Enter '1' to be notified of an automatic backorder or cancel. \_\_\_\_\_  
Enter '2' to be notified but not create the backorder or cancel.  
Enter '3' to create the backorder or cancel automatically and update the order without issuing the warning.
- If left blank, no availability checking will be done.

COMMITMENT CONTROL

- 47. Enter '1' for commitment to Other Quantity 1 or '2' for commitment to Other Quantity 2. This option is typically used in conjunction with a Blanket or Quote Order. If this option is used, the commitment preference will be ignored. \_\_\_\_\_

AUTOMATIC PROCESSING:

- 48. Enter '1' to automatically display the Supply and Demand screen when a new sales detail line is backordered. \_\_\_\_\_
- 49. Enter '1' to print pick slips or a '2' to print invoices through the subsystem. Enter '3' for on-line commitment or a '4' for subsystem commitment. \_\_\_\_\_
- 50. Enter '1' for auto order repricing. \_\_\_\_\_

DREAM WRITER VERSIONS:

- Enter the version for each program.  
If left blank, ZJDE0001 will be used:
- 51. Pick Slip Print (P42520) \_\_\_\_\_
  - 52. Supply and Demand (P4021) \_\_\_\_\_
  - 53. Std Order/Basket Reprice (P421301) \_\_\_\_\_  
or Adv Order/Basket Reprice (P42750) \_\_\_\_\_
  - 54. Customer Service (P42045) \_\_\_\_\_
  - 55. Online Invoice (P42230) \_\_\_\_\_
  - 56. Preference Profile (P40400) \_\_\_\_\_
  - 57. Check Price (Advanced) (P40721) \_\_\_\_\_
  - 58. Customer Master (P01053) \_\_\_\_\_
  - 59. TM Rate & Route server PSMR9100 \_\_\_\_\_

CONFIGURATOR PROCESSING:

- 60. Enter one of the following for the mode of Specification Entry. \_\_\_\_\_  
If left blank, '2' will be used:  
'1' = Text Mode  
'2' = Assisted Mode

'3' = Assisted Prompt Mode

### TRANSFER PRICE UPDATE:

- 61. Enter the order type(s) that the system will use to invoke inter-branch updates. To specify more than one order type, type them one after the other along this field. \_\_\_\_\_
- 62. Enter the transfer pricing method to be used. Default method is 1.  
1 = Branch cost mark-up  
2 = Transfer pricing \_\_\_\_\_
- 63. Enter '1' to allow inter-branch invoicing. If left blank, no inter-branch invoice can be run. \_\_\_\_\_

### WAREHOUSE PROCESSING:

- 64. Enter the request processing mode:  
' ' = No pick requests  
'1' = Generate requests only  
'2' = Generate requests and process using the subsystem \_\_\_\_\_
- 65. If processing pick requests using the subsystem, enter the DREAM Writer version to use. If blank, XJDE0002 is used.  
(See Form ID P46171.) \_\_\_\_\_
- 66. Enter an override next status for sales order lines for which requests have been generated. \_\_\_\_\_

### ORDER TEMPLATE PROCESSING:

- 67. Enter a '1' to use the Sold-to address number for order templates, or a '2' to use the Ship-to address number. If left blank, no automatic order template processing will be performed. \_\_\_\_\_
- 68. Enter the order template name. \_\_\_\_\_

### BLANKET/QUOTE PROCESSING:

- 69. Enter '1' for automatic access to the blanket/quote release processing by Sold To address. Enter '2' for automatic access to the blanket/quote release processing by Ship To address. If left blank, no automatic access to the blanket/quote release processing will be performed. \_\_\_\_\_

### PREFERENCE PROFILE PROCESSING:

- 70. Enter a '1' to use preference profile defaults. If left blank, no preference profile information will be defaulted. \_\_\_\_\_
- 71. Enter a '1' to use the Inventory Commitment Preference to source from multiple branches or to view \_\_\_\_\_

grade or potent items in the  
commitment window.

CURRENCY PROCESSING:

72. Enter the tolerance limit  
percentage to warn you of  
currency rate changes. A 15.0  
indicates a warning if the rate  
is 15 percent greater or less  
than the current rate.

\_\_\_\_\_

LOAD CONFIRM PROCESSING: (ECS)

73. Enter '1' to automatically  
branch to load confirm when order  
are added.

\_\_\_\_\_

74. Enter the version of Bulk Load  
Confirm (P49510) to be used.

\_\_\_\_\_

75. Enter the version of Packaged Load  
Confirm (P49530) to be used.

\_\_\_\_\_

AVIATION/MARINE PROCESSING: (ECS)

76. Enter the version of the Additional  
Parameters program (P49510A) to be  
used.

\_\_\_\_\_

TRIP ASSIGNMENT WINDOW: (ECS)

77. Enter the version of the Trip  
Assignment window (P49200) to be  
used.

\_\_\_\_\_

MARK-FOR ADDRESS PROCESSING:

78. Enter '1' to display Mark-for  
Address.

\_\_\_\_\_



# Configured Items





# Configured Items

## Objectives

- To create a work order for a configured item
- To process a configured item's work order

## About Configured Items

After you enter configured item information during sales order entry, you can work with configured items in other programs within J.D. Edwards Manufacturing and Distribution systems.

Working with configured items consists of the following:

- Processing work orders (required)
- Working with configured string history
- Understanding configured items in Manufacturing systems
- Understanding configured items in Distribution systems






# Process Work Orders

---

## Processing Work Orders



From Manufacturing Systems (G3) choose Configurator Operations.

From Configurator (G32) choose Work Order Processing.

After you have entered configured item sales orders and have created work order headers, you must run the Work Order Generation program to perform the following:

- Generate the work order parts list from the sales order and P type assembly inclusion rules.
- Include additional parts on the work order from Q type assembly inclusion rules.
- Create standard costs for configured items using a sort sequence that is unique to the configured item based on components and attached routings.
- Create the work order routing instructions from the R type assembly inclusion rules.
- Commit inventory.
- Back-schedule configured routings.
- Create one work order for each configured sales order line item. You can also create multiple work orders for a sales order line item. This program does not consolidate work orders for configured items.
- Attach the generic text from a configured item routing to the work order routing.

You can use either subsystem or batch processing of the Work Order Generation program. Batch processing occurs when you run the program. Subsystem processing occurs during sales order entry. However subsystem processing does not produce shop floor paperwork. Subsystem processing is appropriate for new sales orders, not for sales order changes.




For both batch and subsystem processing of Work Order Generation, the sort sequence must be descending by work order number.

## Before You Begin

- Set Configurator Constants for branch or subsystem processing
- Set processing options for the Work Order Generation program for configured item processing

## On Define Subsystem



Complete the following field:

- Option

## What You Should Know About

### Reprocessing a work order

You can run the Work Order Generation program again to reattach the parts list and routing to a configured item.

### Recosting a work order

You can change a work order's parts list and routing and run Work Order Generation again to recost the work order. However, this process eliminates the planned variance for the work order.

<b>Revising the sales order</b>	If you change the sales order after work has been started on the work order, the work order status will change, but the parts list and routing are not affected. Use Configurator Constants to define the status beyond which changes will no longer affect the related work order other than a change in status.
<b>Calculating leadtimes</b>	<p>Work Order Generation calculates each operation's start and end dates and the work order's start date. Work Order Generation back scheduling uses fixed or variable leadtimes that you have defined on Item Location for the work order start date. Because variable leadtimes depend on how the item is configured, you must enter leadtimes manually on Item Location.</p> <p>Work Order Generation calculates leadtimes for multi-level configured items on a multi-level basis, but Leadtime Rollup does not support configured items.</p>
<b>Updating standard costs</b>	Work Order Generation determines a configured item's standard cost from the configured parts list and routing and stores the costs in the Work Order Variance table. This standard cost is also updated to the associated sales order detail line.
<b>Updating sales orders</b>	Use a processing option to control updating the related sales order detail line status.
<b>Starting the subsystem</b>	You can also choose the Start Subsystem menu option.
<b>Stopping the subsystem</b>	You can also choose the Stop Subsystem menu option.
<b>Outside operations</b>	Work Order Generation dynamically calculates costs for outside operations if a configured item's work order includes outside operations.

## See Also

- *Working with the Subsystem (P40105)* in the *Sales Order Management Guide*
- *Processing Work Orders (P31410)* in the *Shop Floor Control Guide*

## Processing Options for Work Order Generation

### GENERATION INFORMATION:

1. Enter one of the following:  
1 - Parts List only
-

## Configuration Management

---

- 2 - Routing only  
3 - Both Parts List and Routing  
If left blank, neither Parts List nor Routing will be generated.
2. Enter a '1' to use the W.O. Date for Effectivity checking. (Default is the W.O. Start Date.) \_\_\_\_\_
- UPDATE INFORMATION:
3. Enter the new Status Code for the Work Order Header. If left blank, status will not be changed. \_\_\_\_\_
- WORK ORDER PRINT INFORMATION:
4. Enter a '1' to print Work Orders. If printing Work Orders: \_\_\_\_\_
- PARTS LIST PRINT INFORMATION:
5. Enter a '1' to print Parts List \_\_\_\_\_  
6. Enter a '1' to print the 2nd line of information, which is scrap and related work center. \_\_\_\_\_  
7. Enter a '1' to print Parts List on a new page. \_\_\_\_\_  
8. Enter the DREAM Writer Version of the Parts List to print. If left blank, XJDE0001 is used. (See Form ID P31415.) \_\_\_\_\_  
9. Enter a '1' to print a consolidated Parts List. \_\_\_\_\_
- ROUTING INSTRUCTIONS PRINT INFO:
10. Enter a '1' to print Routing \_\_\_\_\_  
11. Enter a '1' to print Routing on a new page. \_\_\_\_\_  
12. Enter the DREAM Writer Version to be executed for the desired sequencing of the Routing. If left blank, the operation sequence is used. (See Form ID P314151.) \_\_\_\_\_
- BACKSCHEDULING INFORMATION:
13. Enter the Unit of Measure for backscheduling. \_\_\_\_\_
- SHOP PACKET SUMMARY INFORMATION:
14. Enter a '1' to print the Shop Packet Summary. \_\_\_\_\_
- SHORTAGE REPORT INFORMATION:
15. Enter the DREAM Writer Version of the Shortage Report to execute. If left blank, no shortage report will be printed. (See Form ID P31418.) \_\_\_\_\_
- BAR CODE INFORMATION:
16. Enter the DREAM Writer Version to be executed for the desired print overrides for Bar Coding. (See Form ID P31413.) \_\_\_\_\_
- INVENTORY ISSUE INFORMATION:
17. Enter the DREAM Writer Version of Batch Inventory Issues to execute. If left blank, the Inventory Issues \_\_\_\_\_

program will not be called.  
 (See Form ID P31420)

PURCHASE ORDER INFORMATION:  
 (Used for Sub-Contract Routings)

- 18. Enter the Document Type \_\_\_\_\_
- 19. Enter the Line Type \_\_\_\_\_
- 20. Enter the Beginning Status \_\_\_\_\_
- 21. Enter a '1' to default the tax area from the 'Ship-To' address book number. If left blank, the tax area will default from the Supplier address book number. \_\_\_\_\_

SALES ORDER INFORMATION:

- 22. Enter the new Line Type for kit and configured components. This is used to avoid issuing inventory from Sales Order processing. The Line Type used should be inventory interface 'N'. If left blank, Line Type will not be changed. \_\_\_\_\_
- 23. Enter the Next Status for Sales Order kit and configured component lines. (This is used to bypass the normal flow of the order, i.e., Pick Slip.) If left blank, status will not be changed. \_\_\_\_\_
- 24. Enter a '1' to print Sales Order Text lines. \_\_\_\_\_

CONFIGURED ITEM COSTS:

- 25. Enter one of the following options for calculating the standard cost for configured items in the WO Variance file (F3102). \_\_\_\_\_
  - 1 - Always calculate the standard cost.
  - 2 - Only calculate the standard cost if it has not already been done (no variance records exist.)
 If left blank, standard cost will not be calculated.

BOM SUBSTITUTES:

- 26. Enter '1' to allow the use of Bill of Material substitutes in case of a shortage. \_\_\_\_\_

PURCHASING JOURNAL ENTRIES:

- 27. Enter a '1' to load the Work Order Number into the Subledger field of the purchasing J/E's. \_\_\_\_\_

BLANKET/QUOTE PROCESSING:

- 28. Enter a '1' for automatic blanket order release processing. \_\_\_\_\_

BUILD AGAINST PRIOR REVISIONS:

- 29. Enter a '1' to permit building work orders against prior revision levels. The revision level in the work order header (F4801) will be \_\_\_\_\_

used to select the parts list to attach to the work order. If left blank, prior revision level bills will not be selected.

### WAREHOUSE PROCESSING:

30. Enter the request processing mode: \_\_\_\_\_  
    1 - Generate requests only  
    2 - Generate requests and process using the subsystem.  
    If left blank, requests will not be generated.
31. If processing pick requests using the subsystem, enter the DREAM Writer version to use. If left blank, XJDE0002 will be used. (see Form ID P46171) \_\_\_\_\_
32. Enter the default staging location for moving goods out of the warehouse. The parts picked from the warehouse are staged at this location prior to use within manufacturing. (F1=Location Window) \_\_\_\_\_
33. Enter a '1' if the default staging location should be checked for availability. If the part is available at the staging location a request will NOT be generated. This option only applies to parts without work center locations. \_\_\_\_\_
- GENERIC TEXT PRINT OPTIONS:
35. Enter a '1' to print component generic text on the Parts List. \_\_\_\_\_
36. Enter a '1' to print operation generic text on the Routing. \_\_\_\_\_
37. Enter a '1' to update parts list and routing if order quantity or dates have changed \_\_\_\_\_
38. Enter which symbology to use when using bar codes. \_\_\_\_\_  
    '1' = Code 3 of 9 (Code 39)  
    '2' = Code 128  
    ' ' = Not print bar codes
39. Enter a '1' to prevent commitments for rates. \_\_\_\_\_

## Processing Options for Subsystem Maintenance

### DEFAULT INFORMATION:

1. Enter the default subsystem name. \_\_\_\_\_



### Exercises

See the exercises for this chapter.

# Work with Configured String History

---


## Working with Configured String History

You can generate an additional history of all configured strings that customers order. Review this history by customer and item to analyze sales.

Working with configured string history consists of the following tasks:

- Generating the configured string history
- Reviewing the configured string history

## Generating the Configured String History




From Manufacturing Systems (G3) choose Configurator Operations.

From Configurator (G32) choose Create Segment Value History.

For the sales orders you select, the Create Segment Value History program:

- Retrieves the configured string from the Configured String History table (F3294)
- Separates the string
- Generates a record for each segment value
- Stores the information in the Configured String Segments table (F32942)

You can use this history information to generate custom reports and inquiries.



The system does not generate the Configured String History table (F3295) automatically. You should run the Create Segment Value History program before you can review the history.

## Reviewing the Configured String History



From Manufacturing Systems (G3) choose Configurator Operations.

From Configurator (G32) choose Configured String History.

You can review the configured string history to locate previously ordered configurations at any level of a configured item. The history includes information about customers, orders, price, and cost. You don't have to generate the string history for this review.

You can also view this information during sales order entry, where you can select from previously ordered configured items to enter on the current sales order.


### See Also

- *Working with Configured Item Sales Orders (P4211)*

### ► To review configured string history

---


On Configured String History



1. Complete the following fields:

- Branch Plant
- Configured Item

2. Complete the following optional fields:
  - Order Type
  - Customer Number
  - Order Number
3. Access the detail area to display price and cost information in the following fields:
  - Order
  - Type
  - Price
  - Sold To
  - Cost



Field	Explanation
Customer Number	A number that identifies an entry in the Address Book system. Use this number to identify employees, applicants, participants, customers, suppliers, tenants, and any other Address Book members.
Order Number	The number that identifies an original document. This can be a voucher, an order number, an invoice, unapplied cash, a journal entry number, and so on.
Order/Type	The number that identifies an original document. This can be a voucher, an order number, an invoice, unapplied cash, a journal entry number, and so on.

<b>Field</b>	<b>Explanation</b>
Configured String	This field stores the configured string as it was input on the related sales order.
Req Dated	The date that an item is to arrive or that an action is to be complete.

# Understand Configured Items and Manufacturing

---


## About Configured Items and Manufacturing

After you have entered a configured item sales order, use programs in the Manufacturing system to monitor production of the configured item within the Shop Floor Control and Manufacturing and Distribution Planning systems.

This includes the following:

- Reviewing hours and quantities
- Costing configured items
- Working with work order completions

## Reviewing Hours and Quantities



From Shop Floor Control (G31), choose Daily Order Reporting


From Daily Order Reporting (G3112), choose Order Hours Status

As production continues on a configured item's work order, you must record the hours spent on production and the number of items completed in that time. This allows you to monitor progress and costs and compare them against the standard hours and quantities that you estimated for the job.

After you enter hours and quantities, either manually or through payroll time entry, you can review and revise them before you post them to the Manufacturing system for further tracking and cost accounting.

You can review the quantities entered against the operations scheduled for a configured item's work order, including the actual quantity ordered, completed, and scrapped for each operation. You can also view the standard and variance values, along with the status code, which can be updated for the operation.

Example: Reviewing Hours and Quantities



See Also

- *Reviewing the Status of Hours (P31121) in the Shop Floor Control Guide*
- *Reviewing the Status of Quantities (P31122) in the Shop Floor Control Guide*

## Working With Manufacturing Accounting and Product Costing



From Manufacturing Systems (G3) choose Configurator Operations.

From Configurator (G32) choose Work Order Processing.

Costing for configured items is different from costing for non-configured items. As you manufacture configured items, no engineering variance exists because there is no standard bill of material or routing for the configured item.

The Work Order Processing program calculates the configuration-specific costs. It calculates frozen standard costs for the configured item and updates the unit and extended costs for the sales order. These costs are the accumulation of the components' standard costs, the labor and overhead values defined with manufacturing constants, and the attached routing, work center information, and work order values.

The system stores the configuration-specific standard costs in the Work Order Variance table (F3102) and uses these costs for related Manufacturing Accounting transactions. Configured items do not require rolled frozen standard costs in the Item Cost Component Add-Ons table (F30026). However, standard costs for purchased parts and manufactured parts used by configured items must be frozen (07 Cost Method in F4105) in order to be factored into F3102 standard costs for work orders.



The Product Costing system does not support transfer orders for configured items.

### See Also

- *About Costing Configured Items (P31410)* in the *Product Costing and Manufacturing Accounting Guide*

## Working with Work Order Completions



From Shop Floor Control (G31) choose Daily Order Reporting

From Daily Order Reporting (G3112) choose a Completions option.

The Work Order Completions program uses the information entered in the Shop Floor Control system to create general ledger journal entries. Shop Floor Control creates no interactive journal entries, all journal entries are processed in batch.

For configured items, the system populates new locations with standard costs from the Work Order Variance table so transactions in the Distribution system use the correct costs. The Work Order Completions program will hard commit

the associated sales order and update the sales order's lot and location information.

### See Also

- *Creating Journal Entries (P1802)* in the *Shop Floor Control Guide*



### Exercises

See the exercises for this chapter.

# Understand Configured Items and Distribution

---

## About Configured Items and Distribution

After you have entered a sales order and generated work orders for a configured item, use the following programs in the Distribution system to complete the sales order processing cycle:

- Enter Sales Orders
- Print Pick Slips
- Shipment Confirmation
- Print Invoices
- Print Invoice Journal
- Print G/L Sales Recap
- Update A/R and G/L

## Working with Configured Item Inventory

The Configuration Management system enables you to stock configured items. For stocked configured items, you can use programs within the Distribution system to:


- Review configured strings.
- Review configuration-specific costing information.
- Check availability for configured end items. You can search for segments or for an exact configured string match.
- Select a stocked configured item during sales order entry. The system hard commits the item, does not generate a work order, and uses costs in the Branch/Plant Costs table.
- Perform inventory transactions, such as:
  - Simple issues
  - Transfers
  - Adjustments

The Inventory Management system does not support reclassifications of configured items

### See Also

- *Issuing Inventory (P4112)* in the *Inventory Management Guide*
- *Transferring Inventory (P4113)* in the *Inventory Management Guide*
- *Adjusting Inventory (P4114)* in the *Inventory Management Guide*

### Example: Issues



From Inventory Management (G41), choose Item Master/Transactions

From Item Master/Transactions (G4111), choose Issues

You can perform simple issues on quantities of configured items from locations.

Item Number	Quantity	U/R	Location	Lot
1 FORK LIFT-B	1	TR		

[32053] - Select Configured Items

Functions Options Tools Help


Configured Item FORKLIFT-A Brn/Plt M30  
Forklift, New Improved

Line Quantity  
Total Selected EA  
Quantity Under

0	Quantity	Location	Lot/SN	Brn/Plt	Available
		8662	8662	M30	1
		8663	8663	M30	2
		8664	8664	M30	1
		8665	8665	M30	2

Opt 5=Config Enter=Exit(Save) F3=Exit(None Selected) F24=More

### Example: Transfers



From Inventory Management (G41), choose Item Master/Transactions

From Item Master/Transactions (G4111), choose Transfers

You can transfer configured items from one location to another.

[4112] - Transfers

Functions Options Tools Help

Trans. Date


Document  
Document Type ET Explanation  
Q/L Date

From Branch/Plant M30 To Branch/Plant M30


FROM

0	Item Number	Quantity	U#	Location	Lot
	FORKLIFT-A				

Opt 1=Item Search 2=Reverse F13=Journal Entries F24=More Keys




**Example: Adjustments**



From Inventory Management (G41), choose Item Master/Transactions

From Item Master/Transactions (G4111), choose Adjustments

You can adjust quantities for configured items in a specific location. Configuration Management supports adjustments for locations with existing inventory and adjustments from zero quantity as long as the configuration-specific string history has been defined in the system.



The screenshot shows a window titled "[32053] - Select Configured Items". It has a menu bar with "Functions", "Options", "Tools", and "Help". Below the menu bar are two buttons: a checkmark and an 'X'. The main area contains the following text:

Configured Item: FORKLIFT-A  
 Line Quantity: [blank]  
 Total Selected: EA  
 Quantity Under: [blank]

Brn/Plt: M30  
 Forklift, New Improved

0	Quantity	Location	Lot/SN	Brn/Plt	Available
		8662	8662	M30	1
		8663	8663	M30	2
		8664	8664	M30	1
		8665	8665	M30	2

At the bottom, there is a status bar with the text: "Opt 5=Config Enter=Exit(Save) F3=Exit(None Selected) F24=More". There are also up and down arrow buttons on the right side of the status bar.

## Checking Availability

Use new function keys and options from the Summary and Detailed Availability forms to review the configured item segments.

### Checking Availability During Sales Order Entry

To check availability during sales order entry, you must set the Check Availability field to Y in Configurator Constants. During sales order entry, if the system finds the exact item and string match, all locations containing the specific configuration appear. You can review segment values for all levels of the configured item and select an item used on the sales order. However, no component availability checking is performed.

You can stock configured items and configured subassemblies for sales purposes. You can sell configured subassemblies, but you should not attempt an inventory issue on stocked configured items. Manufacturing Accounting does not support issuing the same stocked configured subassembly part which might have many different costs based on the configuration.



The system does not perform automatic line splitting if the quantity ordered and the quantity selected is different.

#### See Also

- *Working with Configured Item Sales Orders (P4211)*

- *Locating Summary Quantity Information (P41202) in the Sales Order Management Guide*
- *Locating Detailed Quantity Information (P41023) in the Sales Order Management Guide*
- *Reviewing Sales Orders (P42045) in the Sales Order Management Guide*

## Example: Summary Availability




From Item Master/Transactions (G4111), choose Inventory Inquiries

From Inventory Inquiries (G4112), choose Summary Availability

You can use Summary Availability to review inventory locations containing stock for a configured item. Review information such as on-hand, committed, and available quantities for each location.

PS	Location	On Hand	Committed	Available	On Receipt
P		2-		2-	
S	0562	1		1	
S	0563	2		2	
S	0564	1		1	
S	0565	2		2	
S	0566	1	1		
S	0567	2	2		
Totals:		7	3	4	



**Example: Detailed Availability**



From Item Master/Transactions (G4111), choose Inventory Inquiries

From Inventory Inquiries (G4112), choose Detailed Availability

You can use Detailed Availability to review the status of configured items in a specific location. Review information such as on-hand quantity of a configured item and related commitments against that quantity.



## Example: Reviewing Customer Service Information



From Sales Order Management (G42), choose Sales Order Inquiries

From Sales Order Inquiries (G42112), choose Customer Service

Review customer service information to:

- Locate current sales order information from the Sales Detail and the Sales Detail History File tables
- Provide information at the sales order, customer, and item levels
- Change associated text for the sales order line
- Display configuration-specific information

Item	Order	Qty	Sold To	Description	Quantity	Request
9110	00	1	Custom Athletic Br	Forklift Boom	1	04/24/96
9110	00	1	Custom Athletic Br	Forklift Fork	1	04/24/96
9110	00	1	Custom Athletic Br	Chain	1	04/24/96
9110	00	1	Custom Athletic Br	Standard Pump	1	04/24/96
9110	00	44	Custom Athletic Br	Counterweights	44	04/24/96
9110	00	1	Custom Athletic Br	4000 Lb. Chassis	1	04/24/96
9110	00	1	Custom Athletic Br	Gas Engine	1	04/24/96
9110	00	4	Custom Athletic Br	Hard Rubber Tire	4	04/24/96
9110	00	1	Custom Athletic Br	Yellow Paint	1	04/24/96
9110	00	1	Custom Athletic Br	10 Ft Boom	1	04/24/96

## Working with Pick Lists



From Sales Order Inquiries (G42112), choose Sales Order Reports

From Sales Order Reports (G42111), choose Print Pick Slips

After you have generated sales and work orders for configured items, use the Print Pick Slip program to print pick lists. Pick lists include the following information:

- Order quantities picked and moved to the staging or shipping area of the warehouse

## Understand Configured Items and Distribution

- Price by line item basis and for the order as a whole, useful for COD (cash on delivery) deliveries
- Driver's signature line
- Customer signature line, useful for verifying delivery

### Example: Pick Lists

Pick Slip #. . . 12277	J.D. Edwards & Company P I C K S L I P	Page - 1 Date - 4/16/96 Customer No - 4243 Ship To No - 4243 Order Number - 5290-000 SO Related P.O. - Brn/Plt - M30	
Sold To: Custom Athletic Brokers 53104 Peachtree Lane Atlanta GA 30439	Ship To: Custom Athletic Brokers 53104 Peachtree Lane Atlanta GA 30439		

Ord Date	Promised	Customer P.O.	F.O.B.	Ship
03/01/98	03/15/98			Inst

Description	Item Number/Location, Lot	Line	Shipped	Backorder	UM	Price	Extended Amount
Forklift	FORKLIFT	1.000	1		EA	48,500.0000	48,500.00
			Related Order .	13913	Per EA		
*Forklift Boom	BOOM	1.010	1		EA	0.0000	
			Related Order .	13911	Per EA		
*Forklift Fork	FORK	1.020	1		EA	0.0000	
			Related Order .	13912	Per EA		
Cross Member	R115	1.030	1		EA	0.0000	
					Per EA		
Standard Blade	R100	1.040	2		EA	0.0000	
					Per EA		
Chain	B125	1.060	1		EA	0.0000	
					Per EA		
Standard Pump	B100	1.070	1		EA	0.0000	
					Per EA		
Counterweights	F165	1.080	17		EA	0.0000	
					Per EA		
2000 lb. Chassis	F105	1.090	1		EA	0.0000	
					Per EA		
Battery Drive Unit	F130	1.100	1		EA	0.0000	
					Per EA		
Hard Rubber Tire	F175	1.110	4		EA	0.0000	
					Per EA		
Yellow Paint	F150	1.120	1		EA	0.0000	
					Per EA		
8 Ft Boom	F135	1.130	1		EA	0.0000	
					Per EA		
Freight Charge		1.140	1		EA	500.0000	500.00
					Per EA		
Dealer Prep		1.150	1		EA	200.0000	200.00
					Per EA		

Driver Signature	Customer Signature	Shippable Weight	**Final**	Sales Tax	Total Order
			Tax Rt		49,200.00

### See Also

- *Working With Picking Documents (P42520) in the Sales Order Management Guide*

## Working with Shipments




From Sales Order Management (G42), choose Sales Order Processing

From Sales Order Processing (G4211), choose Confirm Shipments

The Configuration Management system supports shipments of configured items. However the system does not allow you to backorder a configured item.

Use the Confirm Shipments program to:

- Locate existing order information
- Add additional line items (non-inventory items only)
- Change the shipped, backorder, and cancel quantities
- Specify a container ID, carrier code, and/or shipment date for each line item
- Override the Ship To Address
- Ship from other or multiple locations
- Adjust inventory (on-hand or hard commits)
- Confirm shipment
- Record serial numbers for shipped items
- Review the Freight/Additional Charges Revisions program



## See Also

- *Working With Shipments (P4205)* in the *Sales Order Management Guide*

## Working with Invoices



From Sales Order Management (G42), choose Sales Order Reports

From Sales Order Reports (G42111), choose Print Invoices

From the Sales Order Reports menu (G42111), choose Print Invoices.

Use the Print Invoices program to print sales order invoices. You can print invoices in proof mode, review them, and then print the invoices and update the files. You can also print invoices in draft mode to review the invoice before updating it. In addition, you can print an invoice from history.

Example: Invoice

J.D. Edwards & Company		Page Number-	1
		Date -	06/25/98
		Customer -	1001
		Brn/Plt -	M30
		Related PO -	145971
		Order Nbr -	9565 SO
		Invoice -	
Sold To: J.D. Edwards & Company Ms. Donna Kirkpatrick Vice-President/CFO 8055 E. Tufts Ave. Suite 1300 Denver CO 80237		Ship To: J.D. Edwards & Company 8055 E. Tufts Ave. Suite 1300 Denver CO 80237	
Tax ID: 45-502499			
Tax Cert:			
Request Date	Customer P.O.	F.O.B.	Ship :
06/25/98			Inst :
Ln/Rq Dt	Description	Item Number	UM Ship/Back/Cance
1.000	*Forklift, New Improved	FORKLIFT-A	EA S
06/25/98			1
			Price
			48,500.0000
			Extended Price
			48,500.00
			Tax
			Y
			Extended Cost
			38,147.95
			Pct
			21
			Per EA
			Sales Tax
			Total Order
Terms	Net 30 Days	Net Due Date 07/25/97	Tax Rt 3.800
			1,843.00
			50,343.00

See Also

- *Working With Invoices (P42565)* in the *Sales Order Management Guide*



Exercises

See the exercises for this chapter.

# Appendices



## Appendix A – Functional Servers

---

Several J.D. Edwards programs access functional servers. The purpose of functional servers is to provide a central location for standard business rules about entering documents, such as vouchers, invoices, and journal entries. These business rules establish the following:

- Data dictionary default values
- Field edits and valid values
- Error processing
- Relationships between fields or applications

The advantages of a functional server are:

- It reduces maintenance of entry programs because edit rules reside in one central location.
- You can standardize documents across all applications because you create them using the same business rules.
- Generally, the user interface (appearance and interaction) of a form is now separate from how a program works.

The steps for setting up business rules for an entry program are:

1. Create a DREAM Writer version for a specific functional server program (for example, XT0411Z1 for voucher entry).
2. Set the processing options within the version according to your company requirements.
3. Specify the version you want the entry program to use in the processing options for that entry program.


You can have all your entry programs use the same DREAM Writer version (and thus, use the same rules) or you can set up different DREAM Writer versions. J.D. Edwards provides DREAM Writer version ZJDE0001 as the default functional server version for your entry programs.



Only the person responsible for system-wide setup should make changes to the functional server version. For more information about how to set up DREAM Writer versions, see the *Technical Foundation Guide*.

## Example: Voucher Processing Functional Server

The following graphic shows the programs that use the voucher processing functional server. J.D. Edwards provides two demo versions of the functional server, ZJDE0001 and ZJDE0002.



# Glossary



# Glossary

---

This glossary defines terms in the context of your use of JDE systems and the accompanying user guide.

**access.** To get to the information or functions provided by the system through menus, screens, and reports.

**allocated material.** Material on hand or on order that is assigned to specific future production or customer orders. Synonymous with *reserved material*.

**alphabetic character.** Represents data by using letters and other symbols from the keyboard (such as \*&#). Contrast with *numeric character*.

**alphanumeric character.** Represents data in a combination of letters, numbers, and other symbols (such as \*&#).

**alternate operation.** Replacement for a normal step in the manufacturing process or routing for an item.

**alternate routing.** A routing, usually less preferred than the primary routing, but resulting in an identical item.

**assemble-to-order.** A make-to-order product for which key components (bulk, semi-finished, intermediate, subassembly, fabricated, purchased, packaging, etc.) used in the assembly or finishing process are planned and stocked in anticipation of a customer order. Receipt of an order initiates assembly of the finished product. This is useful when a large number of finished products can be assembled from common components.

**assembly.** A group of subassemblies and/or parts that are put together and constitute a major subdivision for the final product. An assembly may be an end item or a component of a higher level assembly.

**audit trail.** The detailed, verifiable history of a processed transaction. The history consists of the original documents, transaction entries, and posting of records, and usually concludes with a report.

**automatic accounting instruction (AAI).** A code that points to an account in the chart of accounts. AAIs define rules for programs that automatically generate journal entries. This includes interfaces between Accounts Payable, Accounts Receivable, and Financial Reporting and the General Accounting system. Each system that interfaces with the General Accounting system has AAIs. For example, AAIs can direct the Post to General Ledger program to post a debit to a certain expense account and an automatic credit to a certain accounts payable account.

**backflush.** The deduction from inventory records of the component parts used in an assembly or subassembly by exploding the bill of material by the production count of assemblies produced.

**back scheduling.** A technique for calculating operation start dates and due dates. The schedule is computed starting with the due date for the order and working backward to determine the required start date and/or due dates for each operation.

**backup copy.** A copy of original data preserved on a magnetic tape or diskette as protection against destruction or loss.

**batch.** A group of like records or transactions that the computer treats as a single unit during processing. For identification purposes, the system usually assigns each batch a unique identifier, known as a "batch number."

**batch bill of material.** A bill of material in which the statement of quantity per is based on the standard batch quantity of the parent.

**batch header.** Information the computer uses as identification and control for a group of transactions or records in a batch.

**batch job.** A task or group of tasks you submit for processing that the system treats as a single unit during processing, for example, printing reports and purging files. The computer performs these tasks with little or no user interaction.

**batch processing.** A method by which the computer selects jobs from the job queue, processes them, and writes output to the outqueue. Contrast with *interactive processing*.

**batch type.** A code that designates which JDE system the associated transactions pertain to, thus controlling what records are selected for processing. For example, in the Post General Journal process, only unposted transaction batches with a batch type of G for General Accounting are selected for posting.

**bill of material (BOM).** A listing of all the subassemblies, parts, and raw materials that go into a parent assembly showing the quantity of each required to make the assembly. It is used in conjunction with the master production schedule to determine the items for which purchase requisitions and production orders must be released. There is a variety of display formats for bills of material, including: single level, multi level, indented, planning, and costed. Synonymous with *formula*, *recipe*, and *ingredients list*.

**Boolean logic operand.** In JDE's DREAM Writer, the parameter of the Relationship field. The Boolean logic operand tells the system to perform a comparison between certain records or parameters. Available operands are:

EQ = Equal To  
LT = Less Than

LE = Less Than or Equal To  
GT = Greater Than  
GE = Greater Than or Equal To  
NE = Not Equal To  
NL = Not Less Than  
NG = Not Greater Than

**bubble chart.** A diagram that attempts to display the interrelationships of systems, functions, or data in sequential flow. It derives its name from the circular symbols used to enclose the statements on the chart.

**bucketed system.** An MRP, DRP, or other time-phased system in which all time-phased data are accumulated into time periods or "buckets." If the period of accumulation is one week, then the system is said to have weekly buckets.

**bucketless system.** An MRP, DRP, or other time-phased system in which all time-phased data are processed, stored, and usually displayed using dated records rather than defined time periods or "buckets."

**bulk issue.** Parts issued from stores to work-in-process inventory, but not based on a job order. They are issued in quantities estimated to cover requirements of individual work centers and production lines. The issue may be used to cover a period of time or to fill a fixed-size container.

**by-product.** A material of value produced as residual of or incidental to the production process. The ratio of by-product to primary product is usually predictable. By-products may be recycled, sold as is, or used for other purposes.

**CAD/CAP.** Computer Assisted Design/Computer Assisted Programming. A set of automated programming tools for designing and developing systems. These tools automate system design, generate source code and documentation, enforce design standards, and help to ensure consistency throughout all JDE systems.

---

**capacity requirements planning (CRP).**

The function of establishing, measuring, and adjusting limits or levels of capacity. It is the process of determining in detail how much labor and machine resources are required to accomplish the tasks of production. Open shop orders and planned orders in the MRP system are input to CRP, which "translates" these orders into hours of work by work center and by time period.

**category code.** In user defined codes, a temporary title for an undefined category. For example, if you are adding a code that designates different sales regions, you could change *category code 4* to *Sales Region*, and define E (East), W (West), N (North), and S (South) as the valid codes. Category codes were formerly known as *reporting codes*.

**character.** Any letter, number, or other symbol that a computer can read, write, and store.

**closed-loop MRP.** A system built around material planning that includes the additional planning functions of sales and operations (production planning, master production scheduling, and capacity requirements planning). Once this planning phase is complete and the plans have been accepted as realistic and attainable, the execution functions come into play. These include the manufacturing control functions of input-output (capacity) measurement, detailed scheduling and dispatching, as well as anticipated delay reports from both the plant and supplier. The term "closed loop" implies that not only is each of these elements included in the overall system, but also that feedback is provided by the execution functions so that the planning can be kept valid at all times.

**command.** A character, word, phrase, or combination of keys you use to tell the computer to perform a defined activity.

**component.** Raw material, ingredient, part, or subassembly that goes into a higher level assembly, compound, or other item. This term may also include packaging materials for finished items.

**component availability.** The availability of component inventory for the manufacture of a specific parent order or group of orders or schedules.

**constants.** Parameters or codes that rarely change. The computer uses constants to standardize information processing by an associated system. Some examples of constants are allowing or disallowing out-of-balance postings and having the system perform currency conversions on all amounts. Once you set constants such as these, the system follows these rules until you change the constants.

**Core.** The central and foundational systems of JDE software, including General Accounting, Accounts Payable, Accounts Receivable, Address Book, Financial Reporting, Financial Modeling and Allocations, and Back Office.

**costed bill of material.** A form of bill of material that extends the quantity per of every component in the bill by the cost of the components.

**crew size.** The number of people required to perform an operation. The associated standard time should represent the total time for all crew members to perform the operation, not the net start to finish time for the crew.

**cumulative leadtime.** The longest planned length of time involved to accomplish the activity in question. For any item planned through MRP, it is found by reviewing the leadtime for each bill of material path below the item. Whichever path adds up to the greatest number defines cumulative leadtime. Synonymous with *aggregate leadtime*, *composite leadtime*, and *critical path leadtime*.

**cumulative manufacturing leadtime.**

The cumulative planned leadtime when all purchased items are assumed to be in stock.

**cumulative MRP.** The planning of parts and subassemblies by exploding a master schedule, as in MRP, except that the master scheduled items and therefore the exploded requirements are time phased in cumulative form. Usually these cumulative figures cover a planning year.

**current cost.** The current or replacement cost of labor, material, or overhead. Its computation is based on current performance or measurements, and it is used to address "today's" costs before production as a revision of annual standard costs.

**cursor.** The blinking underscore or rectangle on your screen that indicates where the next keystroke will appear.

**cursor sensitive help.** JDE's online help function, which allows you to view a description of a field, an explanation of its purpose, and, when applicable, a list of the valid codes you can enter. To access this information, move the cursor to the field and press F1.

**data.** Numbers, letters, or symbols that represent facts, definitions, conditions, and situations, that a computer can read, write, and store.

**database.** A continuously updated collection of all information a system uses and stores. Databases make it possible to create, store, index, and cross-reference information online.

**data dictionary.** A database file consisting of the definitions, structures, and guidelines for the usage of fields, messages, and help text. The data dictionary file does not contain the actual data itself.

**default.** A code, number, or parameter the system supplies when you do not enter one. For example, if an input field's default is N and the you do not enter something in that field, the system supplies an N.

**demand.** A need for a particular product or component. The demand could come from any number of sources, such as a customer order or forecast, or an interplant requirement or a request from a branch warehouse for a service part or for manufacturing another product.

**dependent demand.** Demand that is directly related to or derived from the bill of material structure for other items or end products. Such demands are calculated and need not and should not be forecast. A given inventory item may have both dependent and independent demand at any given time. For example, a part may simultaneously be the component of an assembly and also sold as a service part.

**descriptive title.** See *user defined code*.

**detail.** The individual pieces of information and data that make up a record or transaction. Contrast with *summary*.

**detail file.** A file which contains manufacturing, routing, or specification details. Contrast with *master file*.

**direct labor.** Labor that is specifically applied to the product being manufactured or utilized in the performance of the service.

**direct material.** Material that becomes a part of the final product in measurable quantities.

**discrete manufacturing.** Production of distinct items such as automobiles, appliances, or computers.

**display.** (1) To cause the computer to show information on a terminal's screen. (2) A specific set of fields and information that a JDE system might show on a screen. Some screens can show more than one display when you press a specified function key.

**display field.** A field of information on a screen that contains a system-provided code or parameter that you cannot change. Contrast with *input field*.

---

**downstream operation.** A task subsequent to the task currently being planned or executed.

**DREAM Writer.** Data Record Extraction And Management Writer. A flexible data manipulator and cataloging tool. You use this tool to select and sequence the data that is to appear on a programmed report.

**edit.** (1) To make changes to a file by adding, changing, or removing information. (2) The program function of highlighting fields into which you have entered inadequate or incorrect data.

**effectivity date.** The date on which a component or an operation is to be added or removed from a bill of material or an assembly process. The effective dates are used in the explosion process to create demands for the correct items. Normally, bill of material and routing systems provide for an effectivity "start date" (from) and "stop date" (thru), signifying the beginning and end of a particular relationship. Synonymous with *effective date*.

**efficiency.** A measure (as a percentage) of the actual output to the standard output expected. Efficiency measures how well something is performing relative to expectations; it does not measure output relative to any input. For example, if there is a standard of 100 pieces per hour and 780 units are produced in one eight-hour shift, the efficiency is 780 divided by 800, then multiplied by 100% or 97.5%.

**electronic data interchange (EDI).** The paperless (electronic) exchange of trading documents, such as purchase orders, shipment authorizations, advanced shipment notices, and invoices, using standardized document formats.

**end item.** A product sold as a completed item or repair part. Any item subject to a customer order or sales forecast. Synonymous with *end product*, *finished good*, and *finished product*.

**engineering change order (ECO).** A work order used to implement a change in a manufactured product. This can be a change in design, quantity or parts required, assembly or production process, and so forth.

**engineer-to-order.** Products whose customer specifications require unique engineering design or significant customization. Each customer order results in a unique set of part numbers, bills of material, and routings.

**execute.** See *run*.

**exit.** (1) To interrupt or leave a computer program by pressing a specific key or a sequence of keys. (2) An option or function key displayed on a screen that allows you to access another screen.

**expedite.** To "rush" or "chase" production or purchase orders that are needed in less than the normal leadtime. To take extraordinary action because of an increase in relative priority.

**facility.** A collection of computer language statements or programs that provides a specialized function throughout a system or throughout all integrated systems. Some examples DREAM Writer and FASTR.

**FASTR.** Financial Analysis Spreadsheet Tool and Report Writer. A report writer that allows you to design your own report specifications using the general ledger database.

**feature.** An accessory or attachment to an item.

**field.** (1) An area on a screen that represents a particular type of information, such as name, document type, or amount. Fields that you can enter data into are designated with underscores. See *input field* and *display field*. (2) A defined area within a record that contains a specific piece of information. For example, a vendor record

consists of the fields Vendor Name, Address, and Telephone Number. The Vendor Name field contains just the name of the vendor.

**file.** A collection of related data records organized for a specific use and electronically stored by the computer.

**fixed cost.** An expenditure that does not vary with the production volume, for example, rent, property tax, and salaries of certain personnel.

**fixed order quantity.** A lot-sizing technique in MRP or inventory management that will always cause planned or actual orders to be generated for a predetermined fixed quantity, or multiples thereof, if net requirements for the period exceed the fixed order quantity.

**fixed overhead.** Traditionally all manufacturing costs, other than direct labor and direct materials, that continue even if products are not produced. Although fixed overhead is necessary to produce the product, it cannot be directly traced to the final product.

**fold area.** An area of a screen, accessed by pressing F4, that displays additional information associated with the records or data items displayed on the screen.

**forecast.** An estimate of future demand. A forecast can be determined by mathematical means using historical data, created subjectively by using estimates from informal sources, or a combination of both techniques.

**function.** A separate feature within a facility that allows you to perform a specific task, for example, the field help function.

**function key.** A key you press to perform a system operation or action. For example, you press F4 to have the system display the fold area of a screen.

**Gantt chart.** A control chart designed to show graphically the relationship between planned performance and actual performance.

**hard copy.** A presentation of computer information printed on paper. Synonymous with *printout*.

**header.** Information at the beginning of a file. This information is used to identify or provide control information for the group of records that follows.

**help instructions.** Online documentation or explanations of fields that you access by pressing the Help key or by pressing F1 with your cursor in a particular field.

**helps.** See *help instructions*.

**hidden selections.** Menu selections you cannot see until you enter HS in a menu's Selection field. Although you cannot see these selections, they are available from any menu. They include such items as Display Submitted Jobs (33), Display User Job Queue (42), and Display User Print Queue (43). The Hidden Selections window displays three categories of selections: user tools, operator tools, and programmer tools.

**implode.** 1) Compression of detailed data in a summary-level record or report. 2) Tracing a usage and/or cost impact from the bottom to the top (end product) of a bill of material using where-used logic.

**implosion.** The process of determining the where-used relationship for a given component. Implosion can be single-level (showing only the parents on the next higher level) or multilevel (showing the ultimate top-level parent). Synonymous with *where used*. Contrast with *explosion*.

**indented bill of material.** A form of multilevel bill of material that lists the highest level parent items at the left margin and all the components going into these parents indented to the right of the margin. All subsequent levels of components are indented farther to the right. If a component is used in more than one parent within a given product structure, it will appear more than once, under every subassembly in which it is used.

---

**indented where-used.** A listing of every parent item, and the respective quantities required, as well as each of their respective parent items, continuing until the ultimate end item, or level-0 item, is listed. Each of these parent items is one that calls for a given component item in a bill of material file. The component item is shown closest to the left margin of the listing, with each parent indented to the right, and each of their respective parents indented even further to the right.

**indirect costs.** Costs that are not directly incurred by a particular job or operation. Certain utility costs, such as plant heating, are often indirect. An indirect cost is typically distributed to the product through the overhead rates.

**indirect labor.** Work required to support production in general without being related to a specific product, for example, sweeping the floor.

**indirect materials.** Items that become part of the final product or substances that are consumed in the manufacture of a product that have a negligible value relative to the value of the final product or the usage of which cannot be effectively determined. These components may or may not be included in the bill of material. Synonymous with *supplies*.

**input.** Information you enter in the input fields on a screen or that the computer enters from other programs, then edits and stores in files.

**input field.** An area on a screen, distinguished by underscores ( \_ \_ ), where you type data, values, or characters. A field represents a specific type of information such as name, document type, or amount. Contrast with *display field*.

**install system code.** The code that identifies a JDE system. Examples are 01 for the Address Book system, 04 for the Accounts Payable system, and 09 for the General Accounting system.

**interactive processing.** A job the computer performs in response to commands you enter from a terminal. During interactive processing, you are in direct communication with the computer, and it might prompt you for additional information during the processing of your request. See *online*. Contrast with *batch processing*.

**interface.** A link between two or more JDE systems that allows these systems to send information to and receive information from one another.

**issue.** The physical movement of items from a stocking location and, often, the transaction reporting of this activity.

**issue cycle.** The time required to generate a requisition for material, pull the material from an inventory location, and move it to its destination.

**item.** Any unique manufactured or purchased part, material, intermediate, subassembly, or product.

**item master record.** The master record for an item. Typically, it contains identifying and descriptive data and control values (leadtimes, lot sizes, etc.) and may contain data on inventory status, requirements, planned orders, and costs. Item records are linked together by product structure records which define the bill of material for an item.

**item number.** A number that serves to uniquely identify an item. Synonymous with *part number*.

**jargon.** A JDE term for system specific help text. You base your help text on a specific reporting code you designate in the Data Dictionary Glossary. You can display this text as part of online help.

**job.** A single identifiable set of processing actions you tell the computer to perform. You start jobs by choosing menu selections, entering commands, or pressing designated function keys. An example of a computer job is check printing in the Accounts Payable system.

**job queue.** A screen that lists the batch jobs you and others have told the computer to process. When the computer completes a job, the system removes the job's identifier from the list.

**justify.** To shift information you enter in an input field to the right or left side of the field. Many of the facilities within JDE systems justify information. The system does this only after you press Enter.

**Just-in-Time (JIT).** A philosophy of manufacturing based on planned elimination of all waste and continuous improvement of productivity. The primary elements of zero inventories are to have only the required inventory when needed; to improve quality to zero defects; to reduce leadtimes by reducing setup times, queue lengths, and lot sizes; to incrementally revise the operations themselves; and to accomplish these things at minimum cost.

**key field.** A field common to each record in a file. The system uses the key field designated by the program to organize and retrieve information from the file.

**Key General Ledger Account (Key G/L).** See *automatic accounting instructions*.

**labor cost.** The dollar amount of added value due to labor performed during manufacturing.

**leading zeros.** A series of zeros that certain facilities in JDE systems place in front of a value you enter. This normally occurs when you enter a value that is smaller than the specified length of the field. For example, if you enter 4567 in a field that accommodates eight numbers, the facility places four zeros in front of the four numbers you enter. The result would look like this: 00004567.

**leadtime.** 1) A span of time required to perform a process (or series of operations).  
2) In a logistics context, the time between

recognition of the need for an order and the receipt of goods. Individual components of leadtime can include order preparation time, queue time, move or transportation time, and receiving and inspection time.

**leadtime offset.** A technique used in MRP where a planned order receipt in one time period will require the release of that order in an earlier time period based on the leadtime for the item.

**level.** Every part or assembly in a product structure is assigned a level code signifying the relative level in which that part or assembly is used within the product structure. Normally the end items are assigned to level 0 with the components and subassemblies going into it assigned to level 1 and so forth. The MRP explosion process starts from level 0 and proceeds downward one level at a time.

**level of detail.** (1) The degree of difficulty of a menu in JDE software. The levels of detail for menus are as follows:

- A=Major Product Directories
- B=Product Groups
- 1=Basic Operations
- 2=Intermediate Operations
- 3=Advanced Operations
- 4=Computer Operations
- 5=Programmers
- 6=Advanced Programmers

Also known as *menu levels*.

(2) The degree to which account information in the General Accounting system is summarized. The highest level of detail is 1 (least detailed) and the lowest level of detail is 9 (most detailed).

**master file.** A computer file that a system uses to store data and information which is permanent and necessary to the system's operation. Master files might contain data or information such as paid tax amounts and vendor names and addresses.

**load.** The amount of planned work scheduled and actual work released for a facility, work center, or operation for a

---

specific span of time. It is usually expressed in terms of standard hours of work or, when items consume similar resources at the same rate, units of production.

**lot.** A quantity produced together and sharing the same production costs and resultant specifications.

**lot number.** A number that identifies a designated group of related items manufactured in a single run or received from a vendor in a single shipment.

**lot number control.** Assignment of unique numbers to each instance of receipt and carrying forth that number into subsequent manufacturing processes so that, in review of an end item, each lot consumed from raw materials through end item can be identified as having been used for the manufacture of this specific end item lot.

**lot number traceability.** Tracking parts by lot numbers to a group of items. This tracking can assist in the tracing of quality problems to their source.

**lot traceability.** The ability to identify the lot or batch numbers of consumption and/or composition for manufactured, purchased, and shipped items. This is a federal requirement in certain regulated industries.

**low-level code.** A number that identifies the lowest level in any bill of material at which a particular component may appear. Net requirements for a given component are not calculated until all the gross requirements have been calculated down to that level. Low-level codes are normally calculated and maintained automatically by the computer software. Synonymous with *explosion level*.

**machine hours.** The amount of time, in hours, that a machine is actually running. Machine hours, rather than labor hours, may be used for planning capacity and scheduling and for allocating costs.

**make-to-order product.** A product that is finished after receipt of a customer's order. The final product is usually a combination of standard items and items custom designed to meet the special needs of the customer. Frequently long leadtime components are planned prior to the order arriving in order to reduce the delivery time to the customer. Where options or other subassemblies are stocked prior to customer orders arriving, the term "assemble-to-order" is frequently used.

**make-to-stock product.** A product that is shipped from finished goods, "off-the-shelf," and therefore is finished prior to a customer order arriving. The master scheduling and final assembly scheduling are conducted at the finished goods level.

**manufacturing leadtime.** The total time required to manufacture an item, exclusive of lower level purchasing leadtime. It includes the time for order preparation, queue, setup, run, move, inspection, and put-away.

**manufacturing resource planning (MRP II)** A method for the effective planning of all resources of a manufacturing company. Ideally, it addresses operational planning in units, financial planning in dollars, and has a simulation capability to answer "what if" questions. It is made up of a variety of functions, each linked together: business planning, sales and operations (production planning), master production scheduling, material requirements planning, capacity requirements planning, and the execution support systems for capacity and material. Output from these systems is integrated with financial reports such as the business plan, purchase commitment report, shipping budget, inventory projections in dollars, etc. Manufacturing resource planning is a direct outgrowth and extension of closed-loop MRP.

**master file.** A computer file that a system uses to store data and information which is permanent and necessary to the system's

operation. Master files might contain data or information such as paid tax amounts and vendor names and addresses.

**master planning.** A classification scheme that includes the following activities: forecasting and order servicing (which together constitute demand management); production and resource planning; and master scheduling (which includes the final assembly schedule, the master schedule, and the rough cut capacity plan).

**master production schedule (MPS).** A detailed statement of how many items are planned to be produced and when. The MPS focuses on products to be made and, through the detailed planning system, identifies the resources (materials, work force, plant equipment and capital) needed and the timing of the need.

**menu.** A screen that displays numbered selections. Each of these selections represents a program. To access a selection from a menu, type the selection number and then press Enter.

**menu levels.** See *level of detail*.

**menu masking.** A security feature of JDE systems that lets you prevent individual users from accessing specified menus or menu selections. The system does not display the menus or menu selections to unauthorized users.

**menu message.** Text that appears on a screen after you make a menu selection. It displays a warning, caution, or information about the requested selection.

**need date.** The date when an item is required for its intended use. In an MRP system, this date is calculated by a bill of material explosion of a schedule and the netting of available inventory against that requirement.

**next number facility.** A JDE software facility you use to control the automatic numbering of such items as new G/L accounts, vouchers, and addresses. It lets you specify your desired numbering system

and provides a method to increment numbers to reduce transposition and typing errors.

**nonsignificant part numbers.** Part numbers that are assigned to each part but do not convey any information about the part. They are identifiers, not descriptors. Contrast with *significant part numbers*.

**numeric character.** Represents data using the numbers 0 through 9. Contrast with *alphabetic character* and *alphanumeric character*.

**offline.** Computer functions that are not under the continuous control of the system. For example, if you were to run a certain job on a personal computer and then transfer the results to a host computer, that job would be considered an offline function. Contrast with *online*.

**online.** Computer functions over which the system has continuous control. Each time you work with a JDE system-provided screen, you are online with the system. Contrast with *offline*. See *interactive processing*.

**online information.** Information the system retrieves, usually at your request, and immediately displays on the screen. This information includes items such as database information, documentation, and messages.

**operand.** See *Boolean logic operand*.

**operation number.** A sequential number, usually two, three, or four digits long, such as 010, 020, 030, and so forth, that indicates the sequence in which operations are to be performed within an item's routing.

**operations sequence.** The sequential steps for an item to follow in its flow through the plant. For instance, operation 1: cut bar stock; operation 2: grind bar stock; operation 3: shape; operation 4: polish; operation 5: inspect and send to stock. This information is normally maintained in the routing file.

---

**option.** A numbered selection from a JDE screen that performs a particular function or task. To select an option, you enter its number in the Option field next to the item you want the function performed on. When available, for example, option 4 allows you to return to a prior screen with a value from the current screen.

**output.** Information the computer transfers from internal storage to an external device, such as a printer or a computer screen.

**output queue.** A screen that lists the spooled files (reports) you have told the computer to write to an output device, such as a printer. After the computer writes a file, the system removes that file's identifier from the online list.

**overhead.** Costs incurred in the operation of a business that cannot be directly related to the individual products or services produced. These costs, such as light, heat, supervision, and maintenance, are grouped in several pools (department overhead, factory overhead, general overhead) and distributed to units of product or service by some standard allocation method.

**overlap.** The percentage that an operation overlaps the previous operation in the sequence. For example, a 20% overlap means that the step can begin when the previous step is 80% complete.

**override.** The process of entering a code or parameter other than the one provided by the system. Many JDE systems offer screens that provide default field values when they appear. By typing a new value over the default code, you can *override* the default. See *default*.

**parameter.** A number, code, or character string you specify in association with a command or program. The computer uses parameters as additional input or to control the actions of the command or program.

**part.** Generally, a material item that is used as a component and is not an assembly, subassembly blend, intermediate, and so forth.

**password.** A unique group of characters that you enter when you sign on to the system that the computer uses to identify you as a valid user.

**pegging.** In MRP, the capability to identify for a given item the sources of its gross requirements and/or allocations. Pegging can be thought of as "live where-used" information.

**picking.** The process of withdrawing from stock the components to make the products or the finished goods to be shipped to a customer.

**pick list.** A document that lists the material to be picked for manufacturing or shipping orders.

**planned order.** A suggested order quantity, release date, and due date created by MRP processing when it encounters net requirements. Planned orders are created by the computer, exist only within the computer, and may be changed or deleted by the computer during subsequent MRP processing if conditions change. Planned orders at one level will be exploded into gross requirements for components at the next lower level. Planned orders, along with released orders, serve as input to capacity requirements planning to show the total capacity requirements by work center in future time periods.

**planning bill of material.** An artificial grouping of items and/or events in bill of material format, used to facilitate master scheduling and/or material planning. Sometimes called a pseudo bill of material.

**planning family.** A group of end items whose similarity of design and manufacture facilitates being planned in aggregate.

**planning horizon.** The amount of time the master schedule extends into the future. This is normally set to cover a minimum of

cumulative leadtime plus time for lot sizing low-level components and for capacity changes of primary work centers.

**primary location.** The designation of a certain storage location as the standard, preferred location for an item.

**printout.** A presentation of computer information printed on paper. Synonymous with *hard copy*.

**print queue.** An online list (screen) of written files that you have told the computer to print. Once the computer prints the file, the system removes the file's identifier from the online list. See *output queue*.

**priority.** The relative importance of jobs. The sequence in which jobs should be worked on.

**process manufacturing.** Production that adds value by mixing, separating, forming, and/or performing chemical reactions. It may be done in either batch or continuous mode.

**processing options.** A feature of the JDE DREAM Writer that allows you to supply parameters to direct the functions of a program. For example, processing options allow you to specify defaults for certain screen displays, control the format in which information gets printed on reports, change the way a screen displays information, and enter "as of" dates.

**program.** A collection of computer statements that tells the computer to perform a specific task or group of tasks.

**program specific help text.** Glossary text that describes the function of a field within the context of the program.

**prompt.** (1) A reminder or request for information displayed by the system. When a prompt appears, you must respond in order to proceed. (2) A list of codes or parameters or a request for information provided by the system as a reminder of the type of information you should enter or action you should take.

**PTF.** Program Temporary Fix. A representation of changes to JDE software, which your organization receives on magnetic tapes or diskettes.

**purchased part.** An item sourced from a supplier.

**purge.** The process of removing records or data from a system file.

**record.** A collection of related, consecutive fields of data the system treats as a single unit of information. For example, a vendor record consists of information such as the vendor's name, address, and telephone number.

**reporting code.** See *category code*.

**reverse image.** Screen text that displays in the opposite color combination of characters and background from what the screen typically displays (for example, black on green instead of green on black).

**quantity per.** The quantity of a component to be used in the production of its parent. This value is stored in the bill of material and is used to calculate the gross requirements for components during the explosion process of MRP.

**queue.** 1) In computers: See job queue, output queue, and print queue.  
2) In manufacturing: A waiting line. The jobs at a given work center waiting to be processed. As queues increase, so do average queue time and work-in-process inventory.

**rated capacity.** The demonstrated capability of a system. Traditionally, capacity is calculated from such data as planned hours, efficiency, and utilization. The rated capacity is equal to hours available x efficiency x utilization.

**rate-based scheduling.** A method for scheduling and producing based on a periodic rate, for example, daily, weekly or monthly. Traditionally, this method has been applied to high-volume and process industries. The concept can be applied within job shops using cellular layouts and

---

mixed-model level schedules where the production rate is matched to the selling rate.

**raw material.** Purchased items or extracted materials that are converted via the manufacturing process into components and/or products. receipt. 1) The physical acceptance of an item into a stocking location. 2) The transaction reporting of this activity.

**record.** A collection of related, consecutive fields of data the system treats as a single unit of information. For example, a vendor record consists of information such as the vendor's name, address, and telephone number.

**release.** The authorization to produce or ship material that has already been ordered.

**repetitive manufacturing.** A form of manufacturing where various items with similar routings are made across the same process whenever production occurs. Products may be made in separate batches or continuously. Production in a repetitive environment is not a function of speed or volume.

**replacement parts.** Parts that can be used as substitutes that differ from completely interchangeable service parts in that they require some physical modification, such as cutting, drilling, and so forth, before they can replace the original part.

**revision level.** A number or letter representing the number of times a document has been changed.

**rework order.** A manufacturing order to rework and salvage defective parts or products.

**resource requirements planning (RRP).** The process of converting the production plan and/or the master production schedule into capacity needs for key resources: work force, machinery, warehouse space,

suppliers' capabilities, and in some cases, money. Comparison of capacity required of items in the MPS to available capacity is usually done for each key resource. Synonymous with *rough cut capacity planning*.

**routing.** A set of information detailing the method of manufacture of a particular item. It includes the operations to be performed, their sequence, the various work centers to be involved, and the standards for setup and run. In some companies, the routing also includes information on tooling, operator skill levels, inspection operations, testing requirements, and so forth.

**run.** To cause the computer to perform a routine, process a batch of transactions, or carry out computer program instructions.

**run size.** See standard batch quantity.

**safety stock.** 1) In general, a quantity of stock planned to be in inventory to protect against fluctuations in demand and/or supply. 2) In the context of master production scheduling, the additional inventory and/or capacity planned as protection against forecast errors and/or short-term changes in the backlog. Overplanning can be used to create safety stock.

**scrap.** Unusable material that results from the production process. It is material outside of specifications and of such characteristics that rework is impractical.

**scrap factor.** A percentage factor in the product structure used to increase gross requirements to account for anticipated loss within the manufacture of a particular product. Synonymous with *scrap rate*.

**scroll.** To use the roll keys to move screen information up or down a screen at a time. When you press the Rollup key, for instance, the system replaces the currently displayed text with the next screen of text if more text is available.

**selection.** Found on JDE menus, selections represent functions that you can access from a given menu. To make a selection, you type its associated number in the Selection field and press Enter.

**setup.** 1) The work required to change a specific machine, resource, work center, or line from making the last good piece of unit A to the first good piece of unit B; 2) Teardown of the just completed production and preparation of the equipment for production of the next scheduled item.

**setup cost.** The costs such as scrap costs, calibration costs, downtime costs, and lost sales associated with preparing the resource for the next product.

**setup leadtime.** The time needed to prepare a manufacturing process to start. Setup leadtime may include run and inspection time for the first piece.

**shelf life.** The amount of time an item may be held in inventory before it becomes unusable.

**shop calendar.** See work day calendar.

**shop floor control (SFC).** A system for utilizing data from the shop floor to maintain and communicate status information on shop orders (manufacturing orders) and on work centers. The major subfunctions of shop floor control are: 1) assigning priority of each shop order, 2) maintaining work-in-process quantity information, 3) conveying shop order status information to the office, 4) providing actual output data for capacity control purposes, 5) providing quantity by location by shop order for work-in-process inventory and accounting purposes, and 6) providing measurement of efficiency, utilization, and productivity of the work force and machines.

**shrinkage.** Reductions of actual quantities of items in stock, in process, or in transit. The loss may be caused by scrap, theft, deterioration, evaporation, and so forth.

**shrinkage factor.** A percentage factor in the item master record that compensates for expected loss during the manufacturing cycle either by increasing the gross requirements or by reducing the expected completion quantity of planned and open orders. The shrinkage factor differs from the scrap factor in that the former affects all uses of the part and its components and the scrap factor relates to only one usage. Synonymous with *shrinkage rate*.

**significant part numbers.** Part numbers that are intended to convey certain information, such as the source of the part, the material in the part, the shape of the part, and so forth. These usually make part numbers longer. Contrast with *nonsignificant part numbers*.

**simulation.** 1) The technique of using representative or artificial data to reproduce in a model various conditions that are likely to occur in the actual performance of a system. It is frequently used to test the behavior of a system under different operating policies. 2) Within MRP II, using the operational data to perform "what if" evaluations of alternative plans to answer the question, "Can we do it?" If yes, the simulation can then be run in the financial mode to help answer the question, "Do we really want to?" Synonymous with *what-if analysis*.

**single level bill of material.** A display of those components that are directly used in a parent item. It shows only the relationships one level down.

**single-level where-used.** A list of each parent in which a specific component is directly used and in what quantity. Done by imploding the bill of material.

**softcoding.** A JDE term that describes an entire family of features that allows you to customize and adapt JDE software to your business environment. These features lessen

---

the need for you to use computer programmers when your data processing needs change.

**software.** The operating system and application programs that tell the computer how and what tasks to perform.

**special character.** Representation of data in symbols that are neither letters nor numbers. Some examples are \* & # /.

**spool.** The function by which the system puts generated output into a storage area to await printing and processing.

**spooled file.** A holding file for output data waiting to be printed or input data waiting to be processed.

**standard batch quantity.** The quantity of a parent that is used as the basis for specifying the material requirements for production. The "quantity per" is expressed as the quantity to make the standard batch quantity, not to make only one of the parent. It is often used by manufacturers that use some components in very small quantities or by process-related manufacturers. Synonymous with *run size*.

**standard costs.** The target costs of an operation, process, or product including direct material, direct labor, and overhead charges.

**standard cost system.** A cost system that uses cost units determined before production. For management control purposes, the standards are compared to actual costs and variances are computed.

**standard hours.** The length of time that should be required to 1) set up a given machine or operation and 2) run one part/assembly/batch/end product through that operation. This time is used in determining machine and labor requirements. It is also frequently used as a basis for incentive pay systems and as a basis of allocating overhead in cost accounting systems.

**subassembly.** An assembly that is used at a higher level to make up another assembly.

**subfile.** An area on the screen where the system displays detailed information related to the header information at the top of the screen. Subfiles might contain more information than the screen can display in the subfile area. If so, use the roll keys to display the next screen of information. See *scroll*.

**submit.** See *run*.

**summary.** The presentation of data or information in a cumulative or totaled manner in which most of the details have been removed. Many of the JDE systems offer screens and reports that are summaries of the information stored in certain files.

**superflush.** A technique to relieve all components down to the lowest level using the complete bill of material, based on the count of finished units produced and/or transferred to finished good inventory.

**system.** A collection of computer programs that allows you to perform specific business tasks. Some examples of applications are Accounts Payable, Inventory, and Order Processing. Synonymous with *application*.

**throughput.** 1) The total volume of production through a facility (machine, work center, department, plant, or network of plants). 2) In theory of constraints, the rate at which the system (firm) generates money through sales.

**time series.** A set of data that is distributed over time, such as demand data in monthly time period occurrences.

**unit cost.** Total labor, material, and overhead cost for one unit of production, for example, one part, one gallon, or one pound.

**unit of measure.** The unit in which the quantity of an item is managed, such as by weight, each, box, package, case, and so forth.

**use as is.** A classification for material that has been dispositioned as unacceptable per the specification, yet can be used.

**user defined code.** The individual codes you create and define within a user defined code type. Code types are used by programs to edit data and allow only defined codes. These codes might consist of a single character or a set of characters that represents a word, phrase, or definition. These characters can be alphabetic, alphanumeric, or numeric. For example, in the user defined code type table ST (Search Type), a few codes are C for Customers, E for Employees, and V for Vendors.

**user defined code (type).** The identifier for a table of codes with a meaning you define for the system (for example, ST for the Search Type codes table in Address Book). JDE systems provide a number of these tables and allow you to create and define tables of your own. User defined codes were formerly known as *descriptive titles*.

**user identification (user ID).** The unique name you enter when you sign on to a JDE system to identify yourself to the system. This ID can be up to 10 characters long and can consist of alphabetic, alphanumeric, and numeric characters.

**valid codes.** The allowed codes, amounts, or types of data that you can enter in a specific input field. The system checks, or edits, user defined code fields for accuracy against the list of valid codes.

**variable.** Changing, not constant or fixed. For example, variable costs are costs that change according to varying conditions.

**variable overhead.** All manufacturing costs that vary directly with production volume, other than direct labor and direct materials. Variable overhead is necessary to produce the product, but cannot be directly assigned to a specific product.

**variance.** The difference between the expected (budgeted or planned) value and the actual value.

**video.** The display of information on your monitor screen. Normally referred to as the *screen*.

**vocabulary overrides.** A JDE facility that allows you to override field, row, or column title text on a screen-by-screen or report-by-report basis.

**where used list.** A listing of every parent item that calls for a given component, and the respective quantity required, from a bill of material file. Synonymous with *implosion*.

**window.** A software feature that allows a part of your screen to function as if it were a screen in itself. Windows serve a dedicated purpose within a facility, such as searching for a specific valid code for a field.

**work center.** A specific production facility, consisting of one or more people and/or machines with identical capabilities, that can be considered as one unit for purposes of capacity requirements planning and detailed scheduling. Synonymous with *load center*.

**work day calendar.** A calendar used in inventory and production planning functions that consecutively numbers only the working days so that the component and work order scheduling may be done based on the actual number of work days available. Synonymous with *planning calendar*, *manufacturing calendar*, and *shop calendar*.

**work in process (WIP).** A product or products in various stages of completion throughout the plant, including all material from raw material that has been released for initial processing up to completely processed material awaiting final inspection and acceptance as finished product. Many accounting systems also include the value

---

of semi-finished stock and components in this category. Synonymous with *in-process inventory*.



# Index



# Index

---

## A

\*RANGE, revising, 2-54, 2-81  
\*VALUE, revising, 2-53

## A

### About

- configuration management tables, 2-87, 2-91
- configured items, 4-1
- configured items in distribution systems, 4-17
- configured items in manufacturing systems, 4-13
- sales orders, 3-1
- setup, 2-2

Advanced Rule Functions form (P32931), 2-82

Advanced rules, setting up, 2-81

AIR Segment Where Used form (P329301), 2-85

Analyzing your configured item, 1-7

Assembly Inclusion form (P3293), 2-72, 2-100

Assembly Inclusion Rules, processing options, 2-83

Assembly inclusion rules, 1-7

- advanced, 2-68
- linking a table to, 2-99
- locating, 2-83
- processing, 2-79
- setting up, 2-67, 2-71

Associated text, working with, 3-16

Associated Text Window form (V401), 3-16

ATO Specification Text Format form (P32941), 3-5

Availability, 4-21

## B

Base Price Revisions form (P4106), 2-22

Bills of material, entering, 2-14

Branch/plant information, 2-10

## C

Checking availability, 4-21

Component information, locating, 2-84

Component Where Used form (P32930), 2-84

Configuration Management

- constants, 2-2
- overview, 1-1
- setup, 2-1

Configuration Management tables, 2-87, 2-91

- calculated value (type C), 2-87, 2-91
- deleting a table value, 2-94
- pricing (type X), 2-87, 2-91
- quantity (types P and Q), 2-87, 2-91
- returning multiple values, 2-96
- setting up, 2-91

Configurator Constants form (P3209), 2-30

Configurator Custom Messages form (P0016), 2-57

Configurator Rules form (P3292W1), 3-15

Configured Item Cross Reference, processing options, 2-96

Configured Item Cross Reference form (P3282), 2-96

Configured item cross-reference, 2-95

- setting up, 2-95

Configured Item Segments form (P3291), 2-35

Configured Item Specifications form (P3294), 3-8, 3-19

Configured items, 1-6, 4-17

- inventory, 4-17
- working with, 4-1

## Configuration Management

---

- working with sales orders, 3-3
- Configured string, 1-6
- Configured string history
  - generating, 4-9
  - reviewing, 4-10
  - working with, 4-9
- Configured String History form (P3296), 3-6, 3-9, 3-12
- Configured String History form (P32961), 4-10
- Constants, setting up, 2-29
- Converting, sales quote to sales order, 3-20
- Copying
  - assembly inclusion rules, 2-83
  - cross segment editing rules, 2-55
- Cross Segment Editing form (P3292), 2-47
- Cross Segment Where Used form (P32920), 2-58
- Cross-reference, generic, 2-96
- Cross-segment editing rules, 1-7
  - reviewing, 2-57
  - setting up, 2-45
- Cross-segment logic, 2-46

## D

- Define Item Price Group form (P4092), 2-24, 2-25
- Define Subsystem form (P40105), 4-4
- Discounting information, setting up, 2-25
- Distribution information, setting up, 2-17
- Distribution systems, configured items, 4-17

## E

- Enter/Change Routing form (P3003), 2-15
- Entering
  - a bill of material for configured items, 2-14
  - a sales order in assisted mode, 3-6
  - a sales order in assisted prompt mode, 3-9
  - a sales order in text mode, 3-4
  - branch/plant information, 2-10
  - custom error message, 2-56
  - item and customer information, 3-4, 3-7, 3-9

- item master information, 2-5
- previously ordered configured item, 3-5, 3-9, 3-11
- routings, 2-14
- Enterprise Requirements Planning and Execution, 1-4
- ERPx, overview, 1-4
- Error messages, 2-45
  - custom, 2-45
    - setting up, 2-56
  - hard, 2-46
  - soft, 2-46
  - system, 2-46
  - working with, 3-14
  - working with hard, 3-14
  - working with soft, 3-15

## Example

- adjustments, 4-20
- checking availability during sales order entry, 4-21
- detailed availability, 4-23
- entering a sales order or a forklift, 1-12
- invoice, 4-28
- issues, 4-18
- pick lists, 4-25
- reviewing customer service information, 4-24
- reviewing tables with column lock, 2-90
- reviewing tables with exact lock, 2-89
- summary availability, 4-22
- transfers, 4-19

## F

- Features, 1-8

## Forms

- Advanced Rule Functions, 2-82
- AIR Segment Where Used, 2-85
- Assembly Inclusion, 2-72, 2-100
- Associated Text window, 3-16
- ATO Specification Text Format, 3-5
- Base Price Revisions, 2-22
- Component Where Used, 2-84
- Configurator Constants, 2-30
- Configurator Custom Messages, 2-57
- Configurator Rules, 3-15
- Configured Item Cross Reference, 2-96
- Configured Item Segments, 2-35

Configured Item Specification, 3-8, 3-19  
 Configured String History, 3-6, 3-9, 3-12, 4-10  
 Cross Segment Editing, 2-47  
 Cross Segment Where used, 2-58  
 Define Item Price Groups, 2-24, 2-25  
 Define Subsystem, 4-4  
 Enter/Change Routing, 2-15  
 Inventory Pricing Rules, 2-26  
 Item Branch/Plant Information, 2-10  
 Item Master Information, 2-6  
 Multi-level Product Selection, 3-18  
 Order Activity Rules, 2-20  
 Order Line Types, 2-18  
 Plant Manufacturing Data, 2-11  
 Rules Copy Window, 2-55, 2-83  
 Sales Order Entry, 1-12, 1-13, 3-5, 3-7, 3-10, 3-11, 3-18, 3-20  
 Segment UDC Where Used, 2-43  
 Segment Value Selection, 3-8  
 Table Definition, 2-93  
 Table Keys, 2-97  
 Table Values, 2-98  
 User Defined Code Revisions, 2-40, 2-93  
 User Defined Code Types, 2-41  
 Value Selection, 2-52, 2-53, 2-80, 2-81

## G

Generating the configured string history, 4-9  
 Graphic
 

- entering a sales order for a forklift, 1-11
- ERPx, 1-4
- menus, 1-10
- system integration, 1-2
- table key, 2-88

## H

Hours, reviewing, 4-13

## I

Inventory Pricing Rules form (P4271), 2-26  
 Invoices, working with, 4-27  
 Item and customer information, entering, 3-4, 3-7, 3-9  
 Item Branch/Plant Information form (P41026), 2-10  
 Item information, setting up, 2-5  
 Item master information, entering, 2-5  
 Item Master Information form (P4101), 2-6

## L

Leadtimes, calculating, 4-5  
 Line types, setting up, 2-18  
 Linking a table to an assembly inclusion rule, 2-99  
 Locating
 

- assembly inclusion rules, 2-84
- component information, 2-84
- segment information, 2-42, 2-85

 Logic statements, 2-45, 2-68

## M

Manufacturing accounting, working with, 4-15  
 Manufacturing systems, configured items, 4-13  
 Menus, 1-10  
 Modes
 

- assisted, 3-3
- assisted prompt, 3-3
- text, 3-3

 Multi-level configured item, 1-6  
 Multi-level Product Selection form (P3298), 3-18

## O

Order activity rules, setting up, 2-19  
 Order Activity Rules form (P40204), 2-20  
 Order Line Types form (P40205), 2-18

Overview, ERPx, 1–4

## P

Pick lists, working with, 4–24

Plant Manufacturing Data form (P41027), 2–11

Previously ordered configured item, entering, 3–5, 3–9, 3–11

Price information, setting up, 2–21

Pricing groups, setting up, 2–23

Printing table information, 2–101

Processing options

Assembly Inclusion Rules, 2–83

Configured Item Cross Reference, 2–96

Sales Order Entry – Detail, 3–21

Subsystem Maintenance, 4–8

Table Definition, 2–95

Table Keys, 2–99

Work Order Generation, 4–5

Processing work orders, 4–3

Product costing, working with, 4–15

Programs and IDs

P00041 (user defined code types), 2–41

P00051 (user defined code revisions), 2–40, 2–93

P0016 (configurator custom messages), 2–57

P3003 (enter/change routing), 2–15

P3209 (configurator constants), 2–30

P3281 (table definition), 2–93

P3282 (configured item cross reference), 2–96

P3283 (table keys), 2–97

P32831 (table values), 2–98

P3291 (configured item segments), 2–35

P32910 (segment UDC where used), 2–43

P3292 (cross segment editing), 2–47

P32920 (cross segment where used), 2–58

P32921 (value selection), 2–52, 2–53, 2–80, 2–81

P3292W1 (configurator rules), 3–15

P3293 (assembly inclusion), 2–72, 2–100

P32930 (component where used), 2–84

P329301 (AIR segment where used), 2–85

P32931 (advanced rule functions), 2–82

P3294 (configured item specifications), 3–8, 3–19

P32941 (ATO specification text format), 3–5

P3295 (segment value selection), 3–8

P3296 (configured string history), 3–6, 3–9, 3–12

P32961 (configured string history), 4–10

P3297 (rules copy window), 2–55, 2–83

P3298 (multi-level product selection), 3–18

P40105 (define subsystem), 4–4

P40204 (order activity rules), 2–20

P40205 (order line types), 2–18

P4092 (define item price groups), 2–24, 2–25

P4101 (item master information), 2–6

P41026 (item branch/plant information), 2–10

P41027 (plant manufacturing data), 2–11

P4106 (base price revisions), 2–22

P42111 (sales order entry), 1–12, 1–13, 3–5, 3–7, 3–10, 3–11, 3–18, 3–20

P4271 (inventory pricing rules), 2–26

V401 (associated text window), 3–16

## R

Ranges, setting up, 2–53, 2–80

Reports

Assembly Inclusion Rules, 2–106

Cross Segment Editing Rules, 2–105

Invoice, 4–28

Pick Lists, 4–25

Segment Rules, 2–104

Reviewing

configured string history, 4–10

cross segment editing rules, 2–57

hours, 4–13

Reviewing quantities, 4–13

Revising a sales order, 3–17

Routings, entering, 2–14

Rules

calculated segment, 2–55

calculation (c), 2–68

component part (p), 2–67

conditional, setting up, 2–72

generic branch/plants set up, 2–56

- multi-level configured items, 2-55
- pricing (x), 2-67
- routing (r), 2-67
- separating, 2-55
- unconditional, to set up, 2-71
- work order component part (q), 2-67

Rules Copy Window form (P3297), 2-55, 2-83

## S

Sales order, 3-1

- assisted mode, entering, 3-6
- assisted prompt mode, entering, 3-9
- configured item, revising, 3-17
- revising, 3-19, 4-5
- text mode, entering, 3-4
- updating, 4-5

Sales order entry, setting up line types, 2-17

Sales Order Entry - Detail, processing options, 3-21

Sales Order Entry form (P42111), 1-12, 1-13, 3-5, 3-7, 3-10, 3-11, 3-18, 3-20

Sales quotes

- configured items, 3-19
- converting to a sales order, 3-20

Segment, 1-6

Segment information, locating, 2-85

Segment UDC Where Used form (P32910), 2-43

Segment Value Selection form (P3295), 3-8

Segments

- calculated, 2-34
- locating, 2-42
- optional, 2-34
- required, 2-33
- setting up, 2-33, 2-35
- setting up values, 2-40

Setting up

- a segment, 2-35
- assembly inclusion rules, 2-71
- configured item cross-reference, 2-95
- constants, 2-29
- cross-segment edit rule error messages, 2-45
- cross-segment editing rules, 2-45
- cross-segment logic, 2-46

- custom error messages, 2-56
- discounting information, 2-25
- distribution information, 2-17
- item information, 2-5
- line types, 2-17
- logic statements in cross-segment editing rules, 2-45
- order activity rules, 2-19
- price information, 2-5
- pricing groups, 2-23
- segments, 2-33
- table dimensions, 2-92
- table values, 2-96
- tables, 2-91
- user defined codes, 2-40

Shipments, working with, 4-26

Standard costs, updating, 4-5

Subsystem

- starting, 4-5
- working with, 4-4

Subsystem Maintenance, processing options, 4-8

System integration, 1-2

## T

Table Definition, processing options, 2-95

Table Definition form (P3281), 2-93

Table dimensions, setting up, 2-92

Table information, printing, 2-101

Table Keys, processing options, 2-99

Table Keys form (P3283), 2-97

Table values, setting up, 2-96

Table Values form (P32831), 2-98

Tables

- Assembly Inclusion Rules (F3293), 1-8
- Base Price (F4106), 1-9
- Branch/Plant (F4102), 1-9
- Configurator Constants (F3209), 1-8
- Configured Item Segments (F3291), 1-8
- Configured Items Rules Table Cross Reference (F3282), 1-9
- Configured String History (F3294), 1-8
- Configured String Master (F32941), 1-9
- Configured String Segment (F32942), 1-9
- Cost Ledger (F4102), 1-9
- Cross Segment Editing Rules (F3292), 1-8
- Item Location (F41021), 1-9

## Configuration Management

---

Item Master (F4101), 1–9  
Range Detail (F32922), 1–8  
Rules Table Definition (F3281), 1–9  
Rules Table Value Definition (F32821),  
1–9  
Sales Order Detail (F4211), 1–9  
Sales Order Header (F4201), 1–9  
Table Detail (F3283), 1–9  
Values Detail (F32921), 1–8  
Terms and concepts, 1–6  
Training class case study, 1–11  
manufacturing accounting, 4–15  
pick lists, 4–24  
shipments, 4–26  
work order completions, 4–15  
Working with sales quotes, 3–19

## U

UDC. *See* User Defined Code  
User Defined Code. *See* UDC  
User Defined Code Revisions form  
(P00051), 2–40, 2–93  
User Defined Code Types form (P00041),  
2–41  
User Defined Codes (UDC), setting up,  
2–40

## V

Value Selection form (P32921), 2–52, 2–53,  
2–80, 2–81  
Values, setting up, 2–52, 2–79

## W

Work order  
  recosting, 4–4  
  reprocessing, 4–4  
Work order completions, 4–15  
Work Order Generation, processing  
options, 4–5  
Work orders, processing, 4–3  
Working with  
  associated text, 3–16  
  configured item inventory, 4–17  
  configured item sales orders, 3–3  
  configured string history, 4–9  
  error messages, 3–14  
  invoices, 4–27