

**Oracle® Communications
Performance Intelligence Center**

ProTraq User Guide

Release 9.0

February 2014

Copyright © 2003, 2014, Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, the following notice is applicable:

U.S. GOVERNMENT RIGHTS Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, duplication, disclosure, modification, and adaptation shall be subject to the restrictions and license terms set forth in the applicable Government contract, and, to the extent applicable by the terms of the Government contract, the additional rights set forth in FAR 52.227-19, Commercial Computer Software License (December 2007). Oracle America, Inc., 500 Oracle Parkway, Redwood City, CA 94065.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information on content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

Table of Contents

PIC..... ERROR! BOOKMARK NOT DEFINED.

TABLE OF CONTENTS **III**

LIST OF FIGURES **5**

LIST OF TABLES..... **6**

CHAPTER 1: OVERVIEW **8**

 OVERVIEW.....14

 SCOPE AND AUDIENCE.....14

 ABOUT THE PERFORMANCE INTELLIGENCE CENTER.....14

User Preferences.....15

 CUSTOMER CARE CENTER22

 PIC DOCUMENTATION LIBRARY23

 LOCATE PRODUCT DOCUMENTATION ON THE CUSTOMER SUPPORT SITE.....24

CHAPTER 2: GETTING STARTED WITH PROTRAQ **25**

 NEW IN THIS RELEASE27

 CONFIGURATION LIMITS.....27

 ACCESSING AND LOGGING INTO NSP28

 PROTRAQ GUI.....29

 PROTRAQ CONFIGURATION VIEW29

ProTraq Configuration View Work Area29

ProTraq Configuration View Tool Bar.....30

ProTraq Configuration View Sessions31

Associated Sessions Listing Tool Bar.....33

Compatible Sessions Listing Tool Bar.....33

 SESSIONS VIEW.....34

Sessions View Work Area.....34

Sessions Listing Tool Bar35

Sessions View Configurations.....36

Sessions View Configurations Tool Bar36

 STATISTIC FLOW VIEW.....37

CHAPTER 3: WORKING WITH PROTRAQ **38**

 MANAGING PROTRAQ CONFIGURATIONS39

 CREATING A CONFIGURATION39

 CONFIGURING PROTRAQ.....42

Configuring rows and columns.....42

Creating a Data Row.....43

Creating a Top Selection Row.....44

Automatic Row Insertion.....46

Creating a Data Column.....47

<i>Creating a Cumulative Counter Column</i>	48
<i>Creating a Ratio Column</i>	50
<i>Creating a Field Value Column</i>	51
<i>Automatic Column Insertion</i>	52
<i>Changing Column or Row Order</i>	53
<i>Modifying a Column or Row</i>	53
<i>Deleting a Column or Row</i>	53
<i>Configuring a corner filter</i>	53
<i>Defining a corner filter</i>	54
<i>Modifying a corner filter</i>	55
<i>Deleting a corner filter</i>	57
<i>Configuring threshold alarms</i>	57
<i>Scheduling a configuration</i>	58
ASSOCIATING AND ACTIVATING SESSIONS	59
<i>Associating xDR Sessions</i>	59
<i>Disassociating a Session</i>	60
<i>Activating xDR Sessions</i>	60
<i>Deactivating xDR Sessions</i>	60
<i>Establishing a ProTraq data flow to an affected Server</i>	61
WORKING WITH EXISTING PROTRAQ CONFIGURATIONS	61
<i>Modifying a configuration</i>	61
<i>Duplicating a configuration</i>	63
<i>Deleting a configuration</i>	64
<i>Creating an aggregated configuration</i>	65
<i>Using the Edition mode to modify configurations</i>	65
FILTERING THE CONFIGURATION AND SESSION LISTINGS	66
IMPORTING AND EXPORTING FILES.....	68
<i>Importing a file into ProTraq</i>	68
<i>Exporting a ProTraq configuration</i>	68
<i>Exporting dependent objects</i>	68
CHAPTER 4: WORKING WITH PROTRAQ RESULTS	70
OVERVIEW	71
PRINCIPLE.....	71
STATISTICS	71
ALARMS	72
USING THE HISTORICAL PROTRAQ APPLICATION FOR KPI CALCULATION ON HISTORICAL XDRs.....	72
TURNING ON TROUBLESHOOTING DRILLDOWN FOR XDR SESSIONS	76
CHAPTER 5: DEFINING AND MODIFYING FLAVOR (PC FORMAT) OF SESSION	78
• DEFINE FLAVOR (PC FORMAT) OF SESSION.....	79
<i>Defining flavor while creating session through xDR DataFlow Assistant</i>	79
<i>Defining flavor while adding Session through session list</i>	79
<i>Defining flavor while defining store DFP</i>	80

MODIFYING FLAVOR OF A XDR SESSION	80
---	----

List of Figures

Figure1: PIC Overview	15
Figure 2: Date/Time Tab Screen	16
Figure 3: Directory Tab Screen.....	17
Figure 4: Mapping Tab Screen	18
Figure 5: Point Code Tab Screen.....	19
Figure 6: Point Code Tab with Session Point Code Enabled.....	20
Figure 7: Formatting Rules (CIC) Screen.....	20
Figure 8: Default Period Tab Screen (ProTrace only).....	21
Figure 9: ProTraq Configuration View Tool Bar	30
Figure 10: Associated Sessions Listing Tool Bar.....	33
Figure 11: Compatible Sessions Listing Tool Bar	33
Figure 12: Sessions Listing Tool Bar	35
Figure 13: Sessions View Configurations Tool Bar	37
Figure 14: Session List.....	39
Figure 15: Associated Session List	60
Figure 16: fse file format	66
Figure 17: Statistics	72
Figure 18: Historical KPI parameters screen.....	73
Figure 19: Historical KPI Protraq config screen	74
Figure 20: Historical KPI Input screen	74
Figure 21: Historical KPI Query screen	75

Figure 22: Historical KPI Output session..... 75

Figure 23: Historical KPI Scheduler screen 75

Figure 24: Historical KPI Summary screen 76

Figure 25: Query Setting Screen 76

Figure 26: Associate flavor while creating session through xDR Data Flow Assistant 79

Figure 27: Associating flavor with Session..... 80

List of Tables

Table 1: Time Tab Screen 17

Table 2: Directory Tab Field Description 17

Table 3: Mapping Tab 18

Table 4: Point Code Tab 19

Table 5: CIC Tab Field Descriptions 21

Table 6: Default Period Tab Field Descriptions..... 22

Table 7: NSP ProTraq Configuration Limits..... 28

Table 8: Configuration Information 30

Table 9: Information Details..... 33

Table 10: Information Details 35

Table 11: Configuration Information..... 36

Table 12: Statistical Storage Setting 40

Table 13: Alarm Setting Details 40

Table 14: Schedule Activation Period Details..... 41

Table 15: Column Types 42

Table 16: Row Types..... 43

Table 17: Row States 43

Table 18: Information for Filter	43
Table 19: Operators.....	44
Table 20: Filter Details	45
Table 21: Operators.....	46
Table 22: Syntax Options	47
Table 23: Filter Details	48
Table 24: Operators.....	48
Table 25: Result Parameters.....	49
Table 26: Filter Details	50
Table 27: Operators.....	50
Table 28: Syntax Options	52
Table 29: Filter Details	54
Table 30: Filter Details	54
Table 31: Operators.....	55
Table 32: Filter Details	56
Table 33: Operators.....	56
Table 34: Operators.....	57
Table 35: Custom Constraint Details	58
Table 36: Alarm Configuration Details.....	59
Table 37: Modifying Configuration Details	62
Table 38: Statistical Storage Settings Details.....	64
Table 39: Alarm settings Information	64
Table 40: Filter Details	67
Table 41: Operators.....	67

Chapter 1: Overview

- **Overview**
- **Scope and Audience**
- **About the Performance Intelligence Center**
- **PIC Documentation Library**

PIC customer documentation and online help are created whenever significant changes are made that affect system operation or configuration. Revised editions of the documentation and online help are distributed and installed on the customer system. Consult your NSP Installation Manual for details on how to update user documentation. Additionally, a Release Notice is distributed on the Tekelec Customer Support site along with each new release of software. A Release Notice lists the PRs that have been resolved in the current release and the PRs that are known to exist in the current release. Listed is the entire PIC documentation library of user guides.

- Security User Guide

- Alarms User Guide
- ProAlarm Viewer User Guide
- ProAlarm Configuration User Guide
- Centralized Configuration Manager Administration Guide
- Customer Care User Guide
- Alarm Forwarding Administration Guide
- Diagnostic Utility Administration Guide
- ProTraq User Guide
- ProPerf User Guide
- ProPerf Configuration User Guide
- System Alarms User Guide
- ProTrace User Guide
- Data Feed Export User Guide
- Audit Viewer Administration Guide
- ProDiag User Guide
- SigTran ProDiag User Guide
- Report Server Platform User Guide
- Reference Data User Guide
- Exported Files User Guide
- Scheduler User Guide
- Quick Start User Guide

Locate Product Documentation on the Customer Support Site

Access to Tekelec's Customer Support site is restricted to current Tekelec customers only. This section describes how to log into the Tekelec Customer Support site and locate a document. Viewing the document requires Adobe Acrobat Reader, which can be downloaded at www.adobe.com.

- a. Log into the [Tekelec Customer Support](#) site.

Note: If you have not registered for this new site, click the Register Here link. Have your customer number available. The response time for registration requests is 24 to 48 hours.
- b. Click the Product Support tab.
- c. Use the Search field to locate a document by its part number, release number, document name, or document type. The Search field accepts both full and partial entries.
- d. Click a subject folder to browse through a list of related files.
- e. To download a file to your location, right-click the file name and select Save Target As.

Chapter 2: Getting Started With ProTraq

- **New in this release**

This release of PIC ProTraq 7.1 includes many changes from the previous versions of ProTraq. General and View improvements:

- Statistic Flow view
- Export Configuration Dependent objects
- Schedule Configuration in the tool bar
- Synchronization Status
- Drill Down not systematically disabled

Parameters and Matrix improvements:

- Matrix and general parameters in one place
- New popup menu on rows / columns
- Insert rows and columns at left and right
- Automatic row and column insertion
- Cut, paste and move rows and columns by drag & drop
- New popup menu on alarms
- Cut and paste alarms
- Multi-Edition alarms
- Create an alarm on an entire column
- Corner, row and column filter queries shared between Protraq & ProTrace
- Automatic backups while editing the configuration
- Configuration Edition in text mode (fse file format)

Configuration limits

In order to perform optimally, the NSP platform operates with certain configuration limits. It is recommended to use these limits for efficient system performance. If a limit range is exceeded or unrecognizable, unexpected results and functioning can occur.

Indicator	System Limit	Recommended Value
Maximum ProTraq configuration rows per configuration	1000	< 1000
Maximum number of cells per configuration	10000	< 500

Configurati on limits for ProTr aq are:

Maximum ProTraq configurations applied to IXP	100	10 per session
Maximum top filter/session	1000	< 10
Maximum results per top	1000	< 100
Maximum field per top filter	1000	
Maximum statistics rows per configuration (including TOPS)	20000	< 20000

limits

- **Accessing and logging into NSP**
- **ProTraq GUI**
- **ProTraq Configuration View**
- **Sessions View**
- **Statistic Flow View**

New in this release

This release of PIC ProTraq 7.1 includes many changes from the previous versions of ProTraq. General and View improvements:

- Statistic Flow view
- Export Configuration Dependent objects
- Schedule Configuration in the tool bar
- Synchronization Status
- Drill Down not systematically disabled

Parameters and Matrix improvements:

- Matrix and general parameters in one place
- New popup menu on rows / columns
- Insert rows and columns at left and right
- Automatic row and column insertion
- Cut, paste and move rows and columns by drag & drop
- New popup menu on alarms
- Cut and paste alarms
- Multi-Edition alarms
- Create an alarm on an entire column
- Corner, row and column filter queries shared between Protraq & ProTrace
- Automatic backups while editing the configuration
- Configuration Edition in text mode (fse file format)

Configuration limits

In order to perform optimally, the NSP platform operates with certain configuration limits. It is recommended to use these limits for efficient system performance. If a limit range is exceeded or unrecognizable, unexpected results and functioning can occur.

Indicator	System Limit	Recommended Value
Maximum ProTraq configuration rows per configuration	1000	< 1000
Maximum number of cells per configuration	10000	< 500
Maximum ProTraq configurations applied to IXP	100	10 per session
Maximum top filter/session	1000	< 10

Configurati
on
limits
for
ProTr
aq
are:

Maximum results per top	1000	< 100
Maximum field per top filter	1000	
Maximum statistics rows per configuration (including TOPS)	20000	< 20000

• L
o
c
a

te Product Documentation on the Customer Support Site

Overview

This user's guide provides information about and procedures for working with ProTraq. It is designed to cover important activities required to use ProTraq.

This user's manual is designed around common tasks that you will perform, with headings and subheadings that allow you to scan the pages easily and zoom in on the information you are interested in. Take some time to browse through these tasks. You may discover things that will make your work with ProTraq more efficient and effective.

Scope and Audience

This user manual provides information about the ProTraq application concepts. It is designed to be both a beginners' guide to working with the ProTraq application and an intermediate and advanced reference to general concepts.

This manual is designed around performing common tasks to efficiently and effectively work with the ProTraq application. Take a few minutes to browse through these tasks and become acquainted with the layout of this guide.

About the Performance Intelligence Center

The Performance Intelligence Center (PIC) is a monitoring and data gathering system that provides network performance, service quality and customer experience - across various networks, technologies, protocols, etc. Beyond monitoring performance and gathering data, the solution also provides analytics, actionable intelligence and potentially an intelligent feedback mechanism. It allows Service Providers to simultaneously look across the Data Link, Network, Transport and Application layer traffic to better correlate and identify the impact of network problems on revenue generating applications and services. PIC functionality is based on the following general flow. The Integrated Message Feeder (IMF) is used to capture SS7 and SigTran traffic. The Probed Message Feeder (PMF) is used to capture both SS7 and IP traffic. Both products forward Probe Data Units (PDUs) to the Integrated xDR Platform (IXP). The IXP stores this traffic data and correlates the data into detailed records (CDRs, IPDRs, TDRs, etc.). The IXP then stores the data on the system for future analysis. The Network Software Platform (NSP) provides applications that mine the detailed records to provide value-added services such as network performance analysis, call tracing and reporting.

PIC centralized configuration tasks fall into one of two categories:

- Data Acquisition and Processing – the configuration of the probes, routing of PDUs to the xDR builder setup, KPI generation, data feeds, etc.
- PIC System Administration - the configuration of monitoring sites, configuring PIC servers, setting up permissions, etc.

Note: For more information see Centralized Configuration Manager Administration Guide. This is a graphic overview of the PIC system.




Figure1: PIC Overview

User Preferences

All applications that query xDRs use a specific User Preferences option. The description outlined goes over the formatting screens.

Note: All screen shots presented here show default values.



Figure 2: Date/Time Tab Screen

a) **Date/Time tab screen:** Format the time parameters.

Field	Description
Date Format	Required field - Sets date format.
Time Format	Required field - Sets time format.
Date and time fields	Required field - Sets the date and time format.
Duration fields	Sets a duration format.
Time Zone	Pull-down list for selecting the desired time zone.
Reset Button	Resets all the tabs to default values.
Reset Tab Button	Resets to default values for the specific tab.
Apply Button	Applies any changes to the system.
Cancel Button	Exits the screen.

Table 1: Time Tab Screen

- b) **Directory tab screen:** Select the Directory tab to set the defaults directories used in transport screen.




Figure 3: Directory Tab Screen

Field	Description
Export Directory	Enables you to set the default directory for exporting.
Upload Directory	Enables you to set the default directory for uploads.
Download Directory	Enables you to set the default directory for downloads.
Reset Button	Resets all the tabs to default values.
Reset Tab Button	Resets to default values for the specific tab.
Apply Button	Applies any changes to the system.
Cancel Button	Exits the screen.

Table 2: Directory Tab Field Description

Note: The directories must be present on the NSP server side. See warning at the bottom of Figure 3: Directory Tab Screen

- c) **Mapping tab:** Select the Mapping tab to set the xDR display parameters.




Figure 4: Mapping Tab Screen

Field	Description
Translate ENUM values	Selects whether ENUM values are translated or not Default is to select ENUM values translation.
Point Code to Node Name	Select this if you want to use the Node Name instead of the Point Code name in the xDR display. Default is to use Node Name.
Link Short Name to Long Name	Selects whether you can use long name (Eagle) for linksets. Default is to use Long Name.
Reset Button	Resets all the tabs to default values.
Reset Tab Button	Resets to default values for the specific tab.
Apply Button	Applies any changes to the system.
Cancel Button	Exits the screen.

Table 3: Mapping Tab

d) **Point Code tab:** Select the Point Code tab, shown and described in the figure and table.




Figure 5: Point Code Tab Screen

Field	Description
Hexadecimal display	European defaults are hexadecimal and display with Group 0-3, Group 1-8, Group 2-3, and Group 3-0.
Decimal display	North American defaults are decimal and display with Group 0-7 and Group 1-5.
Split format	Select or deselect Split format.
Separation	Select a Bit Group Separation.
Group 0	Type a value. (0-7 or 1-5 see hexadecimal or decimal display)
Group 1	Type a value. (0-7 or 1-5 see hexadecimal or decimal display)
Group 2	Type a value. (0-7 or 1-5 see hexadecimal or decimal display)
Group 3	Type a value. (0-7 or 1-5 see hexadecimal or decimal display)
Reset Button	Resets all the tabs to default values.
Reset Tab Button	Resets to default values for the specific tab.
Apply Button	Applies any changes to the system.
Cancel Button	Exits the screen.

Table 4: Point Code Tab

Note: if Session Point Code feature is enabled the Point Code tab will look like




Figure 6: Point Code Tab with Session Point Code Enabled

- e) **CIC tab:** Select the CIC tab to set the parameters for CIC and Bit groups.




Figure 7: Formatting Rules (CIC) Screen

Field	Description
Hexadecimal display	European defaults are hexadecimal and display with Group 0-7 and Group 1-5.
Decimal display	European defaults are hexadecimal and display with Group 0-7 and Group 1-5.
Split format	Select or deselect Split format.
Separation	Select a Bit Group Separation: Group 0:8, Group 1:8.
Group 0	Type a value. (0-7 or 1-5 see hexadecimal or decimal display)
Group 1	Type a value. (0-7 or 1-5 see hexadecimal or decimal display)
Reset Button	Resets all the tabs to default values.
Reset Tab Button	Resets to default values for the specific tab.
Apply Button	Applies any changes to the system.
Cancel Button	Exits the screen.

Table 5: CIC Tab Field Descriptions

- f) **Default Period Tab:** Select the Default Period tab, for setting the default time period for beginning and ending time for traces (ProTrace only).




Figure 8: Default Period Tab Screen (ProTrace only)

Field	Description
-------	-------------

Default Period (in hours)	Sets the default run time period for running traces. Default is 24 hours. Range 1-7200
Reset Button	Resets all the tabs to default values.
Reset Tab Button	Resets to default values for the specific tab.
Apply Button	Applies any changes to the system.
Cancel Button	Exits the screen.

Table 6: Default Period Tab Field Descriptions

After setting the formatting parameters, click **Next** to move to the next screen in the wizard.

Customer Care Center

The Tekelec Customer Care Center is your initial point of contact for all product support needs. A representative takes your call or email, creates a Customer Service Request (CSR) and directs your requests to the Tekelec Technical Assistance Center (TAC). Each CSR includes an individual tracking number. Together with TAC Engineers, the representative will help you resolve your request.

The Customer Care Center is available 24 hours a day, 7 days a week, 365 days a year, and is linked to TAC Engineers around the globe.

Tekelec TAC Engineers are available to provide solutions to your technical questions and issues 7 days a week, 24 hours a day. After a CSR is issued, the TAC Engineer determines the classification of the trouble. If a critical problem exists, emergency procedures are initiated. If the problem is not critical, normal support procedures apply. A primary Technical Engineer is assigned to work on the CSR and provide a solution to the problem. The CSR is closed when the problem is resolved.

Tekelec Technical Assistance Centers are located around the globe in the following locations:

Tekelec - Global

Email (All Regions): support@tekelec.com

USA and Canada

Phone:

1-888-FOR-TKLC or 1-888-367-8552 (toll-free, within continental USA and Canada)

1-919-460-2150 (outside continental USA and Canada)

TAC Regional Support Office Hours:

8:00 a.m. through 5:00 p.m. (GMT minus 5 hours), Monday through Friday, excluding holidays

Caribbean and Latin America (CALA)

Phone:

USA access code +1-800-658-5454, then 1-888-FOR-TKLC or 1-888-367-8552 (toll-free)

TAC Regional Support Office Hours (except Brazil):
10:00 a.m. through 7:00 p.m. (GMT minus 6 hours), Monday through Friday, excluding holidays

- **Argentina**-Phone: 0-800-555-5246 (toll-free)
- **Brazil**- Phone: 0-800-891-4341 (toll-free)
TAC Regional Support Office Hours: 8:30 a.m. through 6:30 p.m. (GMT minus 3 hours),
Monday through Friday, excluding holidays
- **Chile** - Phone: 1230-020-555-5468
- **Colombia** - Phone: 01-800-912-0537
- **Dominican Republic** – Phone : 1-888-367-8552
- **Mexico** – Phone : 001-888-367-8552
- **Peru** – Phone : 0800-53-087
- **Puerto Rico** – Phone :1-888-367-8552 (1-888-FOR-TKLC)
- **Venezuela** - Phone: 0800-176-6497

Europe, Middle East, and Africa

Regional Office Hours: 8:30 a.m. through 5:00 p.m. (GMT), Monday through Friday, excluding holidays

- **Signaling- Phone:** +44 1784 467 804 (within UK)
- **Software Solutions** - Phone: +33 3 89 33 54 00

Asia

- **India** - Phone: +91 124 436 8552 or +91 124 436 8553
TAC Regional Support Office Hours: 10:00 a.m. through 7:00 p.m. (GMT plus 5 1/2 hours),
Monday through Saturday, excluding holidays
- **Singapore** - Phone: +65 6796 2288
TAC Regional Support Office Hours: 9:00 a.m. through 6:00 p.m. (GMT plus 8 hours),
Monday through Friday, excluding holidays

PIC Documentation Library

PIC customer documentation and online help are created whenever significant changes are made that affect system operation or configuration. Revised editions of the documentation and online help are distributed and installed on the customer system. Consult your NSP Installation Manual for details on how to update user documentation. Additionally, a Release Notice is distributed on the Tekelec Customer Support site along with each new release of software. A Release Notice lists the PRs that have been resolved in the current release and the PRs that are known to exist in the current release. Listed is the entire PIC documentation library of user guides.

- Security User Guide
- Alarms User Guide
- ProAlarm Viewer User Guide
- ProAlarm Configuration User Guide
- Centralized Configuration Manager Administration Guide
- Customer Care User Guide
- Alarm Forwarding Administration Guide

- Diagnostic Utility Administration Guide
- ProTraq User Guide
- ProPerf User Guide
- ProPerf Configuration User Guide
- System Alarms User Guide
- ProTrace User Guide
- Data Feed Export User Guide
- Audit Viewer Administration Guide
- ProDiag User Guide
- SigTran ProDiag User Guide
- Report Server Platform User Guide
- Reference Data User Guide
- Exported Files User Guide
- Scheduler User Guide
- Quick Start User Guide

Locate Product Documentation on the Customer Support Site

Access to Tekelec's Customer Support site is restricted to current Tekelec customers only. This section describes how to log into the Tekelec Customer Support site and locate a document. Viewing the document requires Adobe Acrobat Reader, which can be downloaded at www.adobe.com.

- f. Log into the [Tekelec Customer Support](#) site.
Note: If you have not registered for this new site, click the Register Here link. Have your customer number available. The response time for registration requests is 24 to 48 hours.
- g. Click the Product Support tab.
- h. Use the Search field to locate a document by its part number, release number, document name, or document type. The Search field accepts both full and partial entries.
- i. Click a subject folder to browse through a list of related files.
- j. To download a file to your location, right-click the file name and select Save Target As.

Chapter 2: Getting Started With ProTraq

- **New in this release**

This release of PIC ProTraq 7.1 includes many changes from the previous versions of ProTraq. General and View improvements:

- Statistic Flow view
- Export Configuration Dependent objects
- Schedule Configuration in the tool bar
- Synchronization Status
- Drill Down not systematically disabled

Parameters and Matrix improvements:

- Matrix and general parameters in one place
- New popup menu on rows / columns
- Insert rows and columns at left and right
- Automatic row and column insertion
- Cut, paste and move rows and columns by drag & drop
- New popup menu on alarms
- Cut and paste alarms
- Multi-Edition alarms
- Create an alarm on an entire column
- Corner, row and column filter queries shared between Protraq & ProTrace
- Automatic backups while editing the configuration
- Configuration Edition in text mode (fse file format)

Configuration limits

In order to perform optimally, the NSP platform operates with certain configuration limits. It is recommended to use these limits for efficient system performance. If a limit range is exceeded or unrecognizable, unexpected results and functioning can occur.

Indicator	System Limit	Recommended Value
Maximum ProTraq configuration rows per configuration	1000	< 1000
Maximum number of cells per configuration	10000	< 500

Configuration limits for ProTraq are:

Maximum ProTraq configurations applied to IXP	100	10 per session
Maximum top filter/session	1000	< 10
Maximum results per top	1000	< 100
Maximum field per top filter	1000	
Maximum statistics rows per configuration (including TOPS)	20000	< 20000

• C
o
n
f
i
g
u
r
a
t
i
o
n

limits

- **Accessing and logging into NSP**
- **ProTraq GUI**
- **ProTraq Configuration View**
- **Sessions View**
- **Statistic Flow View**

New in this release

This release of PIC ProTraq 7.1 includes many changes from the previous versions of ProTraq. General and View improvements:

- Statistic Flow view
- Export Configuration Dependent objects
- Schedule Configuration in the tool bar
- Synchronization Status
- Drill Down not systematically disabled

Parameters and Matrix improvements:

- Matrix and general parameters in one place
- New popup menu on rows / columns
- Insert rows and columns at left and right
- Automatic row and column insertion
- Cut, paste and move rows and columns by drag & drop
- New popup menu on alarms
- Cut and paste alarms
- Multi-Edition alarms
- Create an alarm on an entire column
- Corner, row and column filter queries shared between Protraq & ProTrace
- Automatic backups while editing the configuration
- Configuration Edition in text mode (fse file format)

Configuration limits

In order to perform optimally, the NSP platform operates with certain configuration limits. It is recommended to use these limits for efficient system performance. If a limit range is exceeded or unrecognizable, unexpected results and functioning can occur.

Indicator	System Limit	Recommended Value
Maximum ProTraq configuration rows per configuration	1000	< 1000
Maximum number of cells per configuration	10000	< 500
Maximum ProTraq configurations applied to IXP	100	10 per session
Maximum top filter/session	1000	< 10

Configuration limits for ProTraq are:

Maximum results per top	1000	< 100
Maximum field per top filter	1000	
Maximum statistics rows per configuration (including TOPS)	20000	< 20000

Table 7: NSP ProTraq Configuration Limits

Accessing and logging into NSP

To access and log into NSP, follow these steps:

- a) Open your Web browser.
- b) In the Address bar, type the following Uniform Resource Locator (URL) for NSP:
<http://nspserver/nsp>, where nspserver is the IP address of NSP.
 Note: NSP only supports versions of IE 7.0 or later and Firefox 3.6 or later. Before using NSP, turn off the browser pop up blocker for the NSP site.

The NSP login screen opens.

Note: Before you can start NSP, you must first have a userid and password assigned to you by your NSP system administrator.

- c) Type your **username** assigned to you in the *Username* field.
- d) Type your **password** in the *Password* field.
- e) Click **OK**.

The NSP Application Board opens.

Click on the *ProTraq* icon to open the application.

--	--

ProTraq GUI

When you access ProTraq, the Main page is displayed. It contains the following:

- A menu bar at the top of the screen
- A menu tree at the left of the screen that displays the available views
- The work area

The menu tree at the left of the screen displays the three available ProTraq views: the Configuration view, the Sessions view and the Statistic Flow View. Each of these views is further explained throughout this document.

The ProTraq work area is set up in a table format. The format changes slightly depending on which view is selected.

Note: Do not use the Function Keys (F1 through F12) when using the NSP. Function keys work in unexpected ways. For example, the F1 key will not open NSP help but will open help for the browser in use. The F5 key will not refresh a specific screen but will refresh the entire session and will result in a loss of any entered information.

ProTraq Configuration View

In the Configuration view, ProTraq configurations display at the top of the work area. When a configuration is highlighted, associated and compatible sessions for that configuration display at the bottom of the work area. The number of records that display in the configuration or session listings can be limited by applying a filter.

ProTraq Configuration View Work Area

The ProTraq configuration view work area displays information in a two-tiered display. In this view, the top part of the work area displays all available configurations and shows the following configuration information:

- Filter - enables a filter to be built for the configuration listing
- All records - applies a filter to the listing by selecting from the drop-down list
- First page - displays the first page of records
- Previous page - displays the previous page of records
- Next page - displays the next page of records
- Last page - displays the last page of records
- Page Size - shows the number of records on each page.
- Set Size - sets the size for the number of records on each page.
- Record number - shows what page you are on in the listing, for example, 21/60 means you are on the 21st page out of 60 total.
- Refresh - refreshes the listing
- Export - exports screen data
- Permissions - sets user privileges
- Create Configuration - creates a configuration
- Modify Configuration - modifies the selected configuration
- Delete Configuration - deletes the selected configuration
- Duplicate Configuration - copies the selected configuration
- Aggregated Configuration - creates a nested configuration
- Synchronize and Activate Configuration - synchronizes and activates the configuration on all associated sessions
- Export ProTraq Configuration - exports the configuration to .fse format
- Export Dependent Objects - exports all dependent objects in .csv format
- Schedule Configuration - schedules the configuration

ProTraq Configuration View Sessions

While using the Configuration view, when a configuration is highlighted in the top of the work area, the bottom displays the sessions currently associated or compatible with the ProTraq configuration. The bottom area of the ProTraq Configuration View screen displays the following two tabs:

- **Associated Sessions tab** - lists all input sessions that are currently associated with the ProTraq configuration. The ProTraq configuration receives data from associated input sessions.
- **Compatible Sessions tab** - lists all non-associated sessions that are compatible with the ProTraq configuration. Any compatible session can be associated with the configuration by clicking the Associate Configuration icon. Once a session is associated, the session moves from the Compatible Sessions listing tab to the Associated Sessions listing tab.

Both tabs include informational columns. Use any of the columns to sort the sessions in the display.

Session	The name of the session associated with the configuration
Start Date	The start date for the session in DD/MM/YYYY format
End Date	The end date for the session in DD/MM/YYYY format

Record Count	The number of records associated with the session
Size (MB)	The size of the records in MBs
Status	<p>The status of the session. This information only displays on the Associated Sessions tab.</p> <p>ACTIVE - ProTraq is generating KPIs IN-ACTIVE - ProTraq is not generating KPIs</p>
Synchronization Status	<p>The synchronization status of the session. This information only displays on the Associated Sessions tab.</p> <p>SYNC - the configuration is identical on NSP and IXP</p> <p>NOT-SYNC - the configuration is not identical on NSP and IXP.</p> <p>Note: All ProTraq configurations are in a NOT-SYNC state after a major upgrade from a previous release to PIC 7.1.</p>
Dictionary Type	<p>Dictionaries describe a session, by providing its column names, titles, syntax, data type, and other information. A dictionary is a text file with an a7d extension that is physically stored on a server. Dictionaries must be present in the NSP database in order for NSP applications to use them. Valid dictionary types are:</p> <ul style="list-style-type: none"> • Capture • Reconstitution • Statistics • SUDR
Format	<p>Archive - Sessions store information in a long-term storage area</p> <p>Single - Sessions store information for a single protocol</p>
Protocol	The protocol of the dictionary
Dictionary	The name of the dictionary used
Subsystem	The subsystem where the session is built and stored

User information	Any additional user information about the configuration
Owner	The owner of the configuration
Creation Time	The time that the configuration was created in DD/MM/YYYY format

Table 9: Information Details

Associated Sessions Listing Tool Bar

The following icons are located on the Associated Sessions listing tool bar:



Figure 10: Associated Sessions Listing Tool Bar

- Filter - enables a filter to be built for the sessions listing
- All records - applies a filter to the listing by selecting from the drop-down list
- First page - displays the first page of records
- Previous page - displays the previous page of records
- Next page - displays the next page of records
- Last page - displays the last page of records
- Page Size - shows the number of records on each page.
- Set Size - sets the size for the number of records on each page.
- Record number - shows what page you are on in the listing, for example, 21/60 means you are on the 21st page out of 60 total.
- Refresh - refreshes the listing
- Export - exports screen data
- Permissions - sets user privileges
- Obtain Session Period and Size - displays specific session information
- Synchronize and Activate Configuration - synchronizes and activates the selected session
- De-Activate Configuration - de-activates the selected session
- Disassociate Configuration - disassociates the session with the configuration and moves the session to the Compatible Sessions tab

Compatible Sessions Listing Tool Bar

The following icons are located on the Compatible Sessions listing tool bar:



Figure 11: Compatible Sessions Listing Tool Bar

- Filter - enables a filter to be built for the sessions listing
- All records - applies a filter to the listing by selecting from the drop-down list
- First page - displays the first page of records
- Previous page - displays the previous page of records
- Next page - displays the next page of records

- Last page - displays the last page of records
- Page Size - shows the number of records on each page.
- Set Size - sets the size for the number of records on each page.
- Record number - shows what page you are on in the listing, for example, 21/60 means you are on the 21st page out of 60 total.
- Refresh - refreshes the listing
- Export - exports screen data
- Permissions - sets user privileges
- Obtain Session Period and Size - displays specific session information
- Associate Configuration - associates the compatible session with the configuration and moves the session to the Associated Sessions tab

Sessions View

In the Sessions view, all sessions display in the top of the work area. When the session is highlighted, all associated configurations display at the bottom of the work area. The number of records that display in the session or configuration listings can be limited by applying a filter.

Sessions View Work Area

The Sessions view displays in a two-tiered display similar to the Configuration view, only the information in the listing is reversed.

In this view, the top part of the screen displays all available sessions. When a session is highlighted in the top of the screen, the bottom of the screen displays the configurations applied to the session. You cannot add additional sessions to a configuration from this view but you can manage privacy permissions for any configuration.

The session listing includes informational columns as sort characteristics. Use any of the information to sort the sessions in the display by using the associated drop down lists.

Session	The name of the session associated with the configuration
Start Date	The start date for the session in DD/MM/YYYY format
End Date	The end date for the session in DD/MM/YYYY format
Record Count	The number of records associated with the session
Size (MB)	The size of the records in MBs

Dictionary Type	Capture Reconstitution Statistics SUDR
Format	Archive Single
Protocol	The protocol of the dictionary
Dictionary	The name of the dictionary used
Subsystem	The subsystem where the session is built and stored
User information	Any additional user information about the configuration
Owner	The owner of the configuration
Creation Time	The time that the configuration was created in DD/MM/YYYY format.

Table 10: Information Details

Sessions Listing Tool Bar

The following icons are located on the Associated Sessions listing tool bar:




Figure 12: Sessions Listing Tool Bar

- Filter - enables a filter to be built for the sessions listing
- All records - applies a filter to the listing by selecting from the drop-down list
- First page - displays the first page of records
- Previous page - displays the previous page of records
- Next page - displays the next page of records
- Last page - displays the last page of records
- Page Size - shows the number of records on each page.
- Set Size - sets the size for the number of records on each page.
- Record number - shows what page you are on in the listing, for example, 21/60 means you are on the 21st page out of 60 total.
- Refresh - refreshes the listing
- Export - exports screen data
- Permissions - sets user privileges
- Obtain Session Period and Size - displays specific session information
- Replace Session - disassociates the session with the configuration and replaces the session with another compatible session as selected from a listing

Sessions View Configurations

The sessions view contains a configuration work area that displays information for configurations associated with the sessions in the listing. The work area shows the following configuration information:

Configuration name	The name of the configuration
Status	Valid statuses are: ACTIVE - ProTraq is generating KPIs IN-ACTIVE - ProTraq is not generating KPIs
Statistical session name	The name of the ProTrace statistical session associated with the configuration
Statistical period	The accounting duration that the configuration works before recoding KPIs. Valid values are 30 seconds, 1 minute, 5 minutes, 15 minutes, 30 minutes, 1 hour, 1 day and 1 week.
Alarms period	The time interval between two threshold controls. Valid values are 30 seconds, 1 minute, 5 minutes, 15 minutes or 30 minutes.
User information	Any additional user information about the configuration
Owner	The owner of the configuration
Creation time	The time that the configuration was created in DD/MM/YYYY format

Table 11: Configuration Information

Use any of the columns to sort the configurations in the display using the drop down lists at the top of each informational column.

When a configuration is highlighted in the top of the work area, the bottom displays the associated and compatible sessions.

Sessions View Configurations Tool Bar

The following icons are located on the Sessions View Configurations tool bar.




Figure 13: Sessions View Configurations Tool Bar

- Filter - enables a filter to be built for the configuration listing
- All records - applies a filter to the listing by selecting from the drop-down list
- First page - displays the first page of records
- Previous page - displays the previous page of records
- Next page - displays the next page of records
- Last page - displays the last page of records
- Page Size - shows the number of records on each page.
- Set Size - sets the size for the number of records on each page.
- Record number - shows what page you are on in the listing, for example, 21/60 means you are on the 21st page out of 60 totals.
- Refresh - refreshes the listing
- Export - exports screen data
- Permissions - sets user privilege

Statistic Flow View

In the Statistical Flow view, all sessions display in the top of the work area. When a session is highlighted a graphical representation of the ProTraq statistical session name, as well as the related ProTraq configurations and input sessions, displays in the bottom of the work area. From this graphical representation, you can tell which configurations are active (green) or inactive (red) and change configuration settings.

Hover mouse over each item in the graphical display to view a description of the item. Double clicking on the graphical representation of a configuration opens up the matrix display, in which you can edit the configuration and view filter or alarm information.

Chapter 3: Working With ProTraq

- **Managing ProTraq configurations**
- **Creating a configuration**
- **Configuring ProTraq**
- **Associating and activating sessions**
- **Working with existing ProTraq configurations**
- **Filtering the configuration and session listings**
- **Importing and exporting files**

Managing ProTraq configurations

This chapter describes the procedures used for adding, modifying, and deleting configurations in ProTraq, as well as the procedures used to configure ProTraq by adding columns, adding rows, and applying filters, activating alarms, scheduling the configuration, associating a session and activating a session.

Creating a configuration

Follow these steps to create a ProTraq configuration.

- From the ProTraq Configuration View screen, click the Create Configuration icon to open the Create a new ProTraq configuration screen. This screen allows you to enter the general parameters that will define your configuration.
- Type in the Configuration Name and any user information. When you've finished, click the Next button.
- Note: Valid characters for the column name are case-sensitive alphanumeric values (A to Z, a to z, 0 to 9) and the underscore (_). The name must start with a letter and is limited to 29 characters with no spaces allowed.
- Enter the protocol name using one of the following methods:
 - Type in any protocol name sequence. ProTraq filters the appropriate entries as you type.
 - Select a protocol using the Select Protocol from button. Select the protocol from either the Sessions tab (which specifies the protocol associated with the session) or the Protocol tab (which specifies an individual protocol). When the protocol is selected, click the "Done" button.

Note: If Session Point Code Feature is enabled then session listing will also show PC Format as one of the fields




Figure 14: Session List

- After selecting the protocol, click the Next button.
- Define the statistical storage settings by entering the following information:

Statistical Session Storage	Valid options are Local Storage (a statistical session is created for each associated xDR session on the same storage as the xDR session) or a specific IXP server (a single statistical session is created on this specific IXP server, used for all associated xDR sessions).
Statistical Session Name	Name of the ProTraq Statistical Session used to store KPIs. Valid characters are case-sensitive alphanumeric values (A to Z, a to z, 0 to 9) and the underscore (_). The name must start with a letter and is limited to 30 characters, no spaces allowed.
Statistical Period	The accounting duration that the configuration works before recoding KPIs. Valid values are 30 seconds, 1 minute, 5 minutes, 15 minutes, 30 minutes, 1 hour, 1 day and 1 week.
Statistical Duration	The length of time (from start to finish) the configuration will collect data in weekly increments up to 15 weeks.

Table 12: Statistical Storage Setting

After entering statistical session information, click the Next button.

- Define the default Alarm settings by entering the following information:

Alarms Period	The time interval between two threshold controls. Valid values are 30 seconds, 1 minute, 5 minutes, 15 minutes or 30 minutes.
Min Record Count	An alarm is raised if a major or minor threshold is reached (TRUE) and the xDR count in the alarm period is equal or greater than the record count value.
Alarm Termination is Constrained	Checking this box terminates the alarm if a major or minor threshold is not reached (FALSE) and the xDR count in the alarm period is equal or greater than the record count value.

Table 13: Alarm Setting Details

After entering alarm settings, click the Next button.

- OPTIONAL STEP:** Set the start and end time for the schedule by selecting the Schedule Activation Period checkbox. That opens the screen where you can fill in the following

information:

Schedule start date	The date when the configuration will begin collecting data in DD/MM/YYYY format.
Schedule start time	The time that the configuration will start collecting data based on a 24 hour clock in HH:MM:SS format.
Period	Start and end times in HH:MM:SS format.
Execute every day	Determines whether the data collection runs on a daily basis. For more complex scheduling, use the Day Scheduling field.
Day Scheduling	Defines more precise scheduling for the data collection. Weekly basic allows you to select specific days of the week, ensuring that the configuration runs from midnight to midnight for the specific day. Monthly basic allows you to select a number of options, for example, a specific day each month (15th, 21st), each day for an entire month, or special days (the 2nd Tuesday of each month).

Table 14: Schedule Activation Period Details

After entering schedule settings, click the Next button.

- Check the parameter settings listed on the summary page. If all the settings are correct, click the Finish button. The configuration is saved and the matrix screen opens, allowing you to add columns and rows to your configuration. For more information see the section on Configuring rows and columns. If you will configure rows and columns at a later time, select the Return to List button to return to the ProTraq Configuration list.

Configuring ProTraq

After general parameters for the ProTraq configuration have been created, configure the following:

- Rows
- Columns
- Corner Filters
- Alarms
- Scheduling the configuration
- Associating and activating sessions

Configuring rows and columns

Configuring rows and columns allow you to collect specific data from the sessions associated with a configuration.

Note: You may not add, modify (except to modify the filter) or delete columns while ProTraq is associated with a session. In order to add or delete columns, you must de-activate and disassociate the configuration from the session, add or delete the columns, and then re-associate the session. The columns and rows in the Matrix display are delineated by their icon.

The following column types are available:

Cumulative Counter	Calculates the sum of a numeric field for all records. Results can display either the lowest sum or highest sum of all selected fields for one record.
Data Counter	Provides the number of xDRs selected in a line, whether all the xDRs or the xDRs matching the filter defined in the column.
Ratio	Calculates the ratio between two prior columns listed in the ProTraq matrix.
Field Value	Provides the value of a field of an xDR or shows the text of a field chosen in a TOP selection line.

Table 15: Column Types

The following row types are available:

Data Row	Allows xDRs to be selected for this row, whether all the xDRs or the xDRs matching the filter defined in the row.
Top	The top selection line enables you to build a list of xDRs with up to ten query fields (filters do not select the xDRs according to given field values).

Table 16: Row Types

The following row states are available:

Exclusive	In an exclusive row, if the row contains a filter, the xDRs that match the filter are removed from the xDR flow and are not processed by the following row.
Non-exclusive	In a non-exclusive row, if the row contains a filter, the xDRs that match the filter are not removed from the xDRs flow and are processed by the following line.

Table 17: Row States

Creating a Data Row

Creating a data row allows all xDRs to be selected for the existing lines, or only xDRs that match a given filter. To create a data row, follow these steps.

- In the Matrix view, right click on an existing row.
- Select to add a row above or below the existing row.
- Select Data as the row type. A summary of the row displays.
- Enter the row name.

Note: The row name can include any alphanumeric characters or symbols. The name is limited to 30 characters and can include spaces.

- Select whether the row is exclusive and select Next.
- Select a filter from the drop down list or build a new filter by entering the following information:

Filter Name	The name of the filter
Description	A description of the filter characteristics

Table 18: Information for Filter

Note: When modifying the filter, the drilldown function is disabled and a warning icon is displayed.

- Select the Add button to add a filter condition. Filter conditions are lettered in capitals. For example, the first one is A, second is B, and the third one is C.
- Select a field from the drop down listing.

Note: When you select a field, the field description is available by clicking on the question mark next to the field name.

- Enter an operator. Valid operators are:

<>	Not equal to
<=	Less than or equal to
>=	Greater than or equal to
>	Greater than
=	Equal to
<	Less than

Table 19: Operators

- Enter a value for the filter or select one from the drop down list.
- To add a second characteristic, determine the operator (And / Or). Select whether the expression should be enclosed in brackets and select the Add button.
- When you have finished adding filter conditions, select Finish. A summary of the row displays, along with a warning icon informing you that the drill down function will be disabled if you save the filter.
- If all the information is correct, select Finish. The row is added to the configuration.

Creating a Top Selection Row

The top selection line enables you to build a list of ten xDRs with up to ten query fields (filters do not select the xDRs according to given field values). These filters build a list of all encountered values of the selected field query filter comparing the top filter fields and, for each field, an encountered value.

You can also group numbers using only a portion of the number. For example, you can group international calls by nationality using only the nation prefix number. You can select part of an address (make sure you give the start position, from left or right, and the length) using the substring function. When the period (statistics or alarms) ends, these virtual lines are sorted in ascending or descending order according to one of the counter values. The N first virtual lines are kept and saved to the statistics session (at the statistics period ending) or checked for alarms at

start or termination (at the alarms period ending).

Note: Top selection filters are dependent on column filters and can only be added if there are column filters present.

Note: You may not add, modify (except to modify the filter) or delete columns while ProTraq is associated with a session. In order to add or delete columns, you must de-activate and disassociate the configuration from the session, add or delete the columns, and then re-associate the session.

To create a TOP selection row, follow these steps. A data counter or cumulative counter column must be created before a TOP row can be added.

- In the Matrix view, right click on an existing row.
- Select to add a row above or below the existing row.
- Select Top Selection as the row type. A summary of the row displays.
- Enter the row name.
Note: The row name can include any alphanumeric characters or symbols. The name is limited to 25 characters and can include spaces.
- Select whether the row is exclusive and select Next.
- Select the fields to be included in the filter by moving available fields from the left of the screen to the right using the arrow buttons. When you've finished selecting fields, select "Next".
- Define the sorting characteristics by selecting the column to sort on and choosing lowest or highest values for the column.
- Define the counters by entering the number of statistical lines in the Top field and the maximum number of xDRs counted by the system during the session. Select Next.
- Select a filter from the drop down list or build a new filter by entering the following information:

Filter Name	The name of the filter
Description	A description of the filter characteristics

Table 20: Filter Details

When modifying the filter, the drilldown function is disabled and a warning icon is displayed.

- Select the Add button to add a filter condition. Filter conditions are lettered in capitals. For example, the first one is A, second is B, and the third one is C.
- Select a field from the drop down listing.
Note: When you select a field, the field description is available by clicking on the question mark next to the field name.
- Enter an operator. Valid operators are:

<>	Not equal to
<=	Less than or equal to
>=	Greater than or equal to
>	Greater than
=	Equal to
<	Less than

Table 21: Operators

- Enter a value for the filter or select one from the drop down list.
- To add a second characteristic, determine the operator (And / Or). Select whether the expression should be enclosed in brackets and select the Add button.
- When you have finished adding filter conditions, select Finish. A summary of the row displays, along with a warning icon informing you that the drill down function will be disabled if you save the filter.
- If all the information is correct, select Finish. The row is added to the configuration.

Automatic Row Insertion

Automatic Row Insertion enables you to create multiple data filtering lines using any single filtering condition you have set up previously. This condition is applied to the same xDR field compared to a given value.

To automatically insert rows, follow these steps.

- In the Matrix view, right click on an existing row.
- Select Automatic Row Insertion.
- Define the condition applied to the row by selecting a field and operator from the drop down lists.
- Select Next.
- To define the rows using existing information, select to load values from a CSV file or from ENUM values.
- To define rows using specific values, select the Add icon.
- Enter the row name syntax. Valid syntax options are:

%n	Name of the item
----	------------------

%v	Value of the filter
%c	Automatic counter

Table 22: Syntax Options

- Enter a filter value.
- To add additional rows, repeat Steps 6 through 8.
- Select Next.
- Verify the information on the Parameter Summary screen. If all the information is correct, select Finish. The column is added to the configuration.

Creating a Data Column

The data counter counts the number of xDRs selected by a row. You can also specify filter information, enabling the column to provide the number of xDRs that match the given filter.

To create a data column, follow these steps.

Note: You may not add, modify (except to modify the filter) or delete columns while ProTraq is associated with a session. In order to add or delete columns, you must de-activate and disassociate the configuration from the session, add or delete the columns, and then re-associate the session.

- In the Matrix view, right click on an existing column.
- Select to add a column to the right or the left of the existing column.
- Select Data as the column type. Select Next.
- Enter the column name and description. Select Next.

Note: Valid characters for the column name are case-sensitive alphanumeric values (A to Z, a to z, 0 to 9) and the underscore (_). The name must start with a letter and is limited to 29 characters with no spaces allowed.

Note: Using the name of a ProTraq default column -- Period End, Duration, Sample, Instance, Corner or Line -- will prevent KPI generation due to duplicate field names. Do not use any of the default names when naming a column.

- Select a filter from the drop down list or build a new filter by entering the following information:

Filter Name	The name of the filter
--------------------	-------------------------------

Description	A description of the filter characteristics
--------------------	---

Table 23: Filter Details

Note: When modifying the filter, the drilldown function is disabled and a warning icon is displayed.

- Select the **Add** button to add a filter condition. Filter conditions are lettered in capitals. For example, the first one is A, second is B, and the third one is C.
- Select a field from the drop down listing.

Note: When you select a field, the field description is available by clicking on the question mark next to the field name.

- Enter an operator. Valid operators are:

<>	Not equal to
<=	Less than or equal to
>=	Greater than or equal to
>	Greater than
=	Equal to
<	Less than

Table 24: Operators

- Enter a value for the filter or select one from the drop down list.
- To add a second characteristic, determine the operator (And / Or). Select whether the expression should be enclosed in brackets and select the Add button.
- When you have finished adding filter conditions, select Finish.
- Verify that the summary information for the column is accurate. If all the information is correct, select Finish. The column is added to the configuration.

Creating a Cumulative Counter Column

A Cumulative counter provides the sum for all the xDRs, or the greatest or the smallest value for a single xDR, of the sum of the chosen field(s) of the xDR.

To create a cumulative counter column, follow these steps.

Note: You may not add, modify (except to modify the filter) or delete columns while ProTraq is associated with a session. In order to add or delete columns, you must de-activate and disassociate the configuration from the session, add or delete the columns, and then re-associate the session.

- In the Matrix view, right click on an existing column.
- Select to add a column to the right or the left of the existing column.
- Select Cumulative Counter as the column type. Select Next.
- Enter the column name and description. Select Next.
- Note: Valid characters for the column name are case-sensitive alphanumeric values (A to Z, a to z, 0 to 9) and the underscore (_). The name must start with a letter and is limited to 29 characters with no spaces allowed.
- Note: Using the name of a ProTraq default column -- Period End, Duration, Sample, Instance, Corner or Line -- will prevent KPI generation due to duplicate field names. Do not use any of the default names when naming a column.
- Select the counters to be included in the column by moving available counters from the left of the screen to the right using the arrow buttons. When you've finished selecting counters, select "Next".
- Select from the following the result parameters:

All	The sum of the selected counter values for each xDR. Result is the sum of those sums.
Keep Lowest	The sum of selected counter values for each xDR. Result is the lowest of those sums.
Keep Highest	The sum of selected counter values for each xDR. Result is the highest of those sums.

Table 25: Result Parameters

- Enter the scale multiplier and the conditions of that multiplier. Valid multipliers are:
 - Bytes to Kilobytes
 - Bytes to Megabytes
 - Bytes to Gigabytes
 - Seconds to minutes
 - Seconds to Hours
 - One to a thousand
 - One to a million
 - One to a billion

- Select a filter from the drop down list or build a new filter by entering the following information:

Filter Name	The name of the filter
Description	A description of the filter characteristics

Table 26: Filter Details

Note: When modifying the filter, the drilldown function is disabled and a warning icon is displayed.

- Select the Add button to add a filter condition. Filter conditions are lettered in capitals. For example, the first one is A, second is B, and the third one is C.
- Select a field from the drop down listing.

Note: When you select a field, the field description is available by clicking on the question mark next to the field name.

- Enter an operator. Valid operators are:

<>	Not equal to
<=	Less than or equal to
>=	Greater than or equal to
>	Greater than
=	Equal to
<	Less than

Table 27: Operators

- Enter a value for the filter or select one from the drop down list.
- To add a second characteristic, determine the operator (And / Or). Select whether the expression should be enclosed in brackets and select the Add button.
- When you have finished adding filter conditions, select Finish.
- Verify that the summary information for the column is accurate. If all the information is correct, select Finish. The column is added to the configuration.

Creating a Ratio Column

A ratio column calculates the ratio between two other columns expressed as an integer or as a percentage. In order to create a ratio column, at least two counter columns must be present in the configuration.

To create a ratio column, follow these steps.

Note: You may not add, modify (except to modify the filter) or delete columns while ProTraq is associated with a session. In order to add or delete columns, you must de-activate and disassociate the configuration from the session, add or delete the columns, and then re-associate the session.

- In the Matrix view, right click on an existing column.
- Select to add a column to the right or the left of the existing column.
- Enter the name of the column and the column description. Select Next.
- Select the field name from the drop down list and select Next.

Note: Valid characters for the column name are case-sensitive alphanumeric values (A to Z, a to z, 0 to 9) and the underscore (_). The name must start with a letter and is limited to 29 characters with no spaces allowed.

Note: Using the name of a ProTraq default column -- Period End, Duration, Sample, Instance, Corner or Line -- will prevent KPI generation due to duplicate field names. Do not use any of the default names when naming a column.

- Select the Value column and Reference column from the available listing.
- To report the ratio as a percentage, select the Express as percentage checkbox. Select Next.
- Verify that the summary information for the column is accurate. If all the information is correct, select Finish. The column is added to the configuration.

Creating a Field Value Column

Field value columns show the value of a field of an xDR or show the text of a field chosen in a Top selection line.

To create a field value column, follow these steps.

Note: You may not add, modify (except to modify the filter) or delete columns while ProTraq is associated with a session. In order to add or delete columns, you must de-activate and disassociate the configuration from the session, add or delete the columns, and then re-associate the session.

- In the Matrix view, right click on an existing column.
- Select to add a column to the right or the left of the existing column.
- Select Field Value as the column type. Select Next.
- Select the field name from the drop down list and select Next.

Note: When you select a field, the field description is available by clicking on the question mark next to the field name.

- Verify that the summary information for the column is accurate. If all the information is correct, select Finish. The column is added to the configuration.

Automatic Column Insertion

Automatic Column Insertion enables you to create multiple data filtering lines using any single filtering condition you have set up previously. This condition is applied to the same xDR field compared to a given value.

To automatically insert columns, follow these steps.

Note: You may not add, modify (except to modify the filter) or delete columns while ProTraq is associated with a session. In order to add or delete columns, you must deactivate and disassociate the configuration from the session, add or delete the columns, and then re-associate the session.

- In the Matrix view, right click on an existing column.
- Select Automatic Column Insertion.
- Define the condition applied to the column by selecting a field and operator from the drop down lists.
- Select Next.
- To define the columns using existing information, select to load values from a CSV file or from ENUM values.
- To define columns using specific values, select the Add icon.
- Enter the column name syntax. Valid syntax options are:

%n	Name of the item
%v	Value of the filter
%c	Automatic counter

Table 28: Syntax Options

- Enter a filter value.
- To add additional columns, repeat Steps 6 through 8.
- Select Next.
- Verify the information on the Parameter Summary screen. If all the information is correct, select Finish. The column is added to the configuration.

Changing Column or Row Order

You can change the order of the columns or rows in your configuration by simply dragging and dropping them into a new position. With the row or column highlighted, hold down the left mouse button until you have the row or column where you want it to be, and then release the mouse button.

Modifying a Column or Row

Follow these steps to modify an existing column or row:

Note: You may not add, modify (except to modify the filter) or delete columns while ProTraq is associated with a session. In order to add or delete columns, you must de-activate and disassociate the configuration from the session, add or delete the columns, and then re-associate the session.

Note: When modifying the filter, the drilldown function is disabled and a warning icon is displayed.

- Select a Column or Row.
- Right click and select the Edit option.
- Modify the appropriate parameters by following the same procedures necessary when adding a column or row.
- When you have finished modifying parameters, select Finish. The column or row is modified.

Deleting a Column or Row

Follow these steps to delete a column or row:

Note: You may not add, modify (except to modify the filter) or delete columns while ProTraq is associated with a session. In order to add or delete columns, you must de-activate and disassociate the configuration from the session, add or delete the columns, and then re-associate the session.

- Right click on the column or row.
- Select the Delete option.
- Select OK on the confirmation screen.

The column or row is removed from the configuration.

Configuring a corner filter

Adding a corner filter to your configuration will filter your input session to limit the type and amount of xDRs sent to the configuration.

Filter Name	The name of the filter
Description	A description of the filter characteristics

Table 29: Filter Details

Note:

- If Session Point code feature is enabled, there is no change in the way Point Code fields are entered while defining filters .Point Codes are entered as default as before when this feature is not enabled .
- Also flavors are not taken into account as the ProTraq configurations are not flavor tagged.
- Queries created in ProTrace can also be used in ProTraq but Point Code will be translated with default flavor.

Defining a corner filter

Use the following steps to create a corner filter:

- In the Matrix view, right click on the corner between the rows and columns.
- Select Define Corner Filter.
- Enter the name to appear on the statistical xDR in the Corner Label field.

Note: Valid characters for the corner filter name are all alphanumeric values (A to Z, a to z, 0 to 9) and all symbols. The name cannot be longer than 30 characters.

- Select Delete accounted records if you do not want the records passed through the corner filter to be saved.
- Select Next.

Note: When modifying the filter, the drilldown function is disabled and a warning icon is displayed.

- Select a filter from the drop down list or build a new filter by entering the following information:

Filter Name	The name of the filter
Description	A description of the filter characteristics

Table 30: Filter Details

- Select the Add button to add a filter condition. Filter conditions are lettered in capitals. For example, the first one is A, second is B, and the third one is C.

- Select a field from the drop down listing.

Note: When you select a field, the field description is available by clicking on the question mark next to the field name.

- Enter an operator. Valid operators are:

<>	Not equal to
<=	Less than or equal to
>=	Greater than or equal to
>	Greater than
=	Equal to
<	Less than

Table 31: Operators

- Enter a value for the filter or select one from the drop down list.
- To add a second characteristic, determine the operator (And / Or). Select whether the expression should be enclosed in brackets and select the Add button.
- When you have finished adding filter conditions, select Finish. The corner filter icon displays, along with a warning icon informing you that the drill down function will be disabled if you save the filter.
- Select Save to save the information.
- Select Return to List to return to the configuration listing.
- To sync the configuration and activate the drill down function, select the Synchronize and Activate Configuration icon.

Modifying a corner filter

To modify an existing corner filter, follow these steps:

- In the Matrix view, right click on the corner between the rows and columns.
- Select Modify Corner Filter.
- Modify the name to appear on the statistical xDR in the Corner Label field.
- Note: Valid characters for the corner filter name are all alphanumeric values (A to Z, a to z, 0 to 9) and all symbols. The name cannot be longer than 30 characters.
- Select Delete accounted records if you do not want the records passed through the corner filter to be saved.
- Select Next.

Note: When modifying the filter, the drilldown function is disabled.

Note:

- Select a filter from the drop down list or build a new filter by entering the following

information: name, description.

Filter Name	The name of the filter
Description	A description of the filter characteristics

Table 32: Filter Details

<>	Not equal to
<=	Less than or equal to
>=	Greater than or equal to
>	Greater than
=	Equal to
<	Less than

- Select the Add button to add a filter condition. Filter conditions are lettered in capitals. For example, the first one is A, second is B, and the third one is C.
- Select a field from the drop down listing.

Note: When you select a field, the field description is available by clicking on the question mark next to the field name.

- Enter an operator. Valid operators are:

Table 33: Operators

- Enter a value for the filter or select one from the drop down list.
- To add a second characteristic, determine the operator (And / Or). Select whether the expression should be enclosed in brackets and select the Add button.
- When you have finished adding filter conditions, select Finish. The corner filter icon displays, along with a warning icon informing you that the drill down function will be disabled if you save the filter.
- Select Save to save the information.
- Select Return to List to return to the configuration listing.
- To sync the configuration and activate the drill down function, select the Synchronize and Activate Configuration icon.

Deleting a corner filter

To delete a corner filter, follow these steps.

- In the Matrix view, right click on the corner between the rows and columns.
- Select Delete Corner Filter.
- Select “Yes” on the confirmation screen.
- Select Return to List to return to the configuration listing.
- To sync the configuration, select the Synchronize and Activate Configuration icon.

Configuring threshold alarms

Alarms configurations are specific to the type of column included in the configuration or session. When configuring alarms, you will see slightly different choices for each column type.

Note: Alarms cannot be configured for a Field Value column since the column is not a counter.

Note: The drill down feature is not available for alarms that occur during an upgrade. Drill down is available on all alarms occurring once the upgrade has been completed.

Use the following steps to configure alarms:

- Highlight the configuration from the listing and select the Modify Configuration icon.
- In the Matrix view, right click on the cell in the row where you want to insert the alarm.
- Define the alarm for the cell by selecting the Plus icon.
- Choose the severity, Min (Minor) or Maj (Major) from the available icons.

Note: You can define only one event per severity.

- Select the operator. Valid values are:

>	Greater than
<	Less than

Table 34: Operators

- Define the threshold for the alarm event.

The alarm threshold for Cumulative Counter and Data Counter columns are expressed as integers.

If you are configuring an integer alarm, skip Step 7 and go to Step 8.

The alarm threshold for a Ratio column is expressed as a percentage if the Express as percentage checkbox is selected. If it is not checked, the column is expressed as an integer. If you are configuring a percentage alarm, go to Step 7.

- Select whether to use a default constraint or a custom constraint. To define a custom constraint, specify the following information.

Counter	Counter name from the drop down list
Minimum Value	The alarm is raised if the minor or major condition is true and if the counter value is greater than the minimum value.
Alarm Termination is constrained	Checking the box will terminate if the minor and major condition is false and if the counter value is equal to or greater than the minimum value.

Table 35: Custom Constraint Details

- When you have finished configuring the alarms, select Finish.
- Select the Save button to save the configuration.
- Select Return to List.

Scheduling a configuration

Follow these steps to schedule a configuration.

- Highlight the configuration in the listing.
- Select the Schedule Configuration icon.
- Set the start and end time for the schedule by selecting the Schedule Activation Period checkbox. That opens the screen where you can fill in the following information:

Schedule start date	In DD/MM/YYYY format
Schedule start time	24 hour clock in HH:MM:SS format
Period	start and end times in HH:MM:SS format
Execute every day	Select to execute the schedule daily
Day Scheduling	Select to define more precise scheduling. Weekly basic allows you to select specific days of the week. Monthly basic allows you to select a number of options, for example, a specific day each month (15th, 21st), each day for an entire month, or special days (The 2nd Tuesday of each month).

Table 36: Alarm Configuration Details

When schedule settings are set, click the Next button.

- Check the parameter settings listed on the summary page. If all the settings are correct, click the Finish button. The configuration is saved and added to the list. Select the Return to List button to see the new configuration.

Associating and activating sessions

When you have completely specified all necessary information for your configuration, you must associate the ProTraq Configuration with one or more sessions and activate the sessions. Associating ProTraq configurations and sessions starts the process for the accumulation of statistical information. Associating sessions links the ProTraq configuration to the input sessions that provide xDRs for the ProTraq KPI generation.

Associating xDR Sessions

Use the following steps to associate xDR sessions to a ProTraq configuration.

- Select a configuration from the listing.
- Select the Compatible Sessions listing from the bottom of the screen.
- Select the Associate Configuration icon.

The session is associated with the configuration and moves from the Compatible Sessions listing to the Associated Sessions listing.

Note: If Session Point Code Feature is enabled then associated session and compatible session list will also show PC Format as one of the fields

Figure 15: Associated Session List

Dictionary Type	Format	Protocol	Dictionary	Subsystem	User Information	PC Format	Owner
All	* All	* All	* All	* All	* All	* All	* All
ECONSTITUTION	SINGLE	LteGtpv2TunnelMgmt	LTE GTP v2 Tunnel Management TDR_1.3.1	ixp1075_Pool	-	NOT APPLICABLE	mcs

Disassociating a Session

You can modify the information compiled by a configuration by disassociating a session from a configuration.

Note: You may not add, modify (except to modify the filter) or delete columns while ProTraQ is associated with a session. In order to add or delete columns, you must de-activate and disassociate the configuration from the session, add or delete the columns, and then re-associate the session. Follow these steps to disassociate a session.

- Select a configuration from the listing.
- Select the Associated Sessions listing from the bottom of the screen.
- Select the Disassociate Configuration icon.

The session is removed from the associated sessions listing. Data configured in that session will no longer be compiled with the configuration.

Activating xDR Sessions

Use the following steps to activate xDR sessions for a ProTraQ configuration.

- Select a configuration from the listing.
- Select the Associated Sessions tab from the bottom of the screen.
- Select the session to be activated and select the Synchronize and Activate Configuration icon. The session status is now active.

Deactivating xDR Sessions

Use the following steps to deactivate xDR sessions.

Note: You may not add, modify (except to modify the filter) or delete columns while ProTraQ is associated with a session. In order to add or delete columns, you must de-activate and disassociate the configuration from the session, add or delete the columns, and then re-associate the session.

- Select a configuration from the listing.
- Select the Associated Sessions tab from the bottom of the screen.
- Select the session to be deactivated and select the De-Activate Configuration icon. The session status changes from active to in-active.

Establishing a ProTraq data flow to an affected Server

Complete these steps to establish a ProTraq data flow to an IXP server.

- Log into Centralized Configuration Manager (CCM).
Note: You log into CCM from the NSP Application Board.
- Select IXP.
- Select Distribution.

The Distribution screen opens.

- Select the appropriate server in the Affected Server.
- Select Streams from the object tree. The Streams screen opens.
- Select DataFlow Processings from the object tree. The Data Flows Processings screen opens.
- Confirm to see if the new data flow records are in the list.

Working with existing ProTraq configurations

After a ProTraq configuration has been created, and additional information has been specified, you can modify, duplicate, delete or created aggregated configurations to further enhance the reporting.

Modifying a configuration

This section outlines how to modify a configuration. Follow these steps to modify a ProTraq configuration.

Note: At any time during this process you may select Restore initial parameters to revert to the last saved version.

- Highlight the configuration in the listing.
- Select the Modify Configuration icon.

The matrix screen opens which displays the details of the configuration.

- Select General Parameters.

This opens up a section where you can modify the configuration details.

Note: While modifying a configuration, the system backs up the configuration information every 5 minutes. Once a backup occurs, the history matrix displays on the screen. The history matrix displays up to 10 automatically backed up versions of the configuration, with the most recent being marked with an asterisk (*). You can revert to a previous version using the drop down list. Regardless of the automatic backup feature, it is recommended that you periodically save your information manually.

- Modify the following information:

Note: The Configuration name and Dictionary cannot be modified.

User Information	Optional information to describe the configuration.
Statistical Session Storage	Valid options are Local Storage (a statistical session is created for each associated xDR session on the same storage as the xDR session) or a specific IXP server (a single statistical session is created on this specific IXP server, used for all associated xDR sessions).
Statistical Session Name	Name of the ProTraQ Statistical Session used to store KPIs. Valid characters are case-sensitive alphanumeric values (A to Z, a to z, 0 to 9) and the underscore (_). The name must start with a letter and is limited to 30 characters, no spaces allowed.
Statistical Period	The accounting duration that the configuration works before recoding KPIs. Valid values are 30 seconds, 1 minute, 5 minutes, 15 minutes, 30 minutes, 1 hour, 1 day and 1 week.
Statistical Duration	The length of time (from start to finish) the configuration will collect data in weekly increments up to 15 weeks.
Alarms Period	The time interval between two threshold controls. Valid values are 30 seconds, 1 minute, 5 minutes, 15 minutes or 30 minutes.
Min Rec Count	An alarm is raised if a major or minor threshold is reached (TRUE) and the xDR count in the alarm period is equal or greater than the record count value.
Alarm Termination is Constrained	Checking this box terminates the alarm if a major or minor threshold is not reached (FALSE) and the xDR count in the alarm period is equal or greater than the record count value.

Table 37: Modifying Configuration Details

- When you've finished modifying the parameters, select the Save button. The configuration is saved and added to the list.
- Select the Return to List button to see the new configuration.

Duplicating a configuration

This section outlines how to copy an existing configuration and save it under a different name. Follow these steps to duplicate a configuration:

- Highlight the configuration in the listing.
- Select the Duplicate Configuration icon. The Duplicate Configuration window opens.
- If the new configuration will be an exact duplicate, change the Configuration name and user information and select the Create Copy button.

A copy of the successfully created duplicate will appear in the configuration listing.

Note: Valid characters for the configuration name are case-sensitive alphanumeric values (A to Z, a to z, 0 to 9) and the underscore (_). The name cannot be longer than 30 characters.

- To change other parameters besides the name and user information, select the Change other parameters before duplicate button.

The Duplicate Configuration window opens.

- Type in the Configuration Name of the record and any user information. When you are finished, click the Next button.
- Note: Valid characters for the configuration name are case-sensitive alphanumeric values (A to Z, a to z, 0 to 9) and the underscore (_). The name cannot be longer than 30 characters.
- The system does not allow you to change the protocol name. To continue, select the Next button.
- Define the statistical storage settings by entering the following information:

Statistical Session Storage	Valid options are Local Storage (a statistical session is created for each associated xDR session on the same storage as the xDR session) or a specific IXP server (a single statistical session is created on this specific ICP server, used for all associated xDR sessions).
Statistical Session Name	Name of the ProTraq Statistical Session used to store KPIs. Valid characters are case-sensitive alphanumeric values (A to Z, a to z, 0 to 9) and the underscore (_). The name must start with a letter and is limited to 30 characters, no spaces allowed.
Statistical Period	The accounting duration that the configuration works before

	recoding KPIs. Valid values are 30 seconds, 1 minute, 5 minutes, 15 minutes, 30 minutes, 1 hour, 1 day and 1 week.
Statistical Duration	The length of time (from start to finish) the configuration will collect data in weekly increments up to 15 weeks.

Table 38: Statistical Storage Settings Details

When you've finished entering statistical session information, click the Next button.

- Define the default
- Alarm settings by entering the following information:

Alarms Period	The time interval between two threshold controls. Valid values are 30 seconds, 1 minute, 5 minutes, 15 minutes or 30 minutes.
Min Record Count	An alarm is raised if a major or minor threshold is reached (TRUE) and the xDR count in the alarm period is equal or greater than the record count value.
Alarm Termination is Constrained	Checking this box terminates the alarm if a major or minor threshold is not reached (FALSE) and the xDR count in the alarm period is equal or greater than the record count value.

Table 39: Alarm settings Information

- Check the parameter settings listed on the summary page. If all the settings are correct, click the Finish button. The configuration is saved and added to the list. Select the Return to List button to see the new configuration.

Deleting a configuration

Follow these steps to delete a ProTraQ configuration.

Note: Before deleting a configuration, you must disassociate and deactivate it in the ProTraQ Configuration listing.

- Highlight the configuration in the listing.
- Select the Delete Configuration icon.

A confirmation window opens for the delete request.

- Select OK.

The configuration is deleted.

Creating an aggregated configuration

An aggregated configuration nests statistical lines coming from different sessions into the same statistical session. This necessitates the initial Protraq configuration (from which the aggregated configuration is created) to have the parameter Storage for statistical session defined as a value different from Local Storage.

Using an aggregated configuration will generate data combined into a single resulting statistical session (aggregation of the same lines coming from different sessions in one cumulative line). Follow these steps to create an Aggregated ProTraq configuration.

- Highlight the configuration in the listing and select the Aggregated Configuration icon. The Create an Aggregated Configuration window displays.
- Type in the Configuration Name of the record and any user information and click the Next button.

Note: Valid characters for the configuration name are case-sensitive alphanumeric values (A to Z, a to z, 0 to 9) and the underscore (_). The name cannot be longer than 30 characters.

- Select the Alarms checkbox to duplicate the alarm settings for the configuration.
- Select the Create Copy button to create the aggregated configuration. The configuration is saved and added to the list.

Using the Edition mode to modify configurations

The Matrix view offers all users with an Administrative role the capability to use the Editions mode functionality, available by selecting the Editions mode icon. The Editions mode allows the ProTraq configuration to be edited in a text mode, in the fse file format.

Note: The Editions mode icon displays in the upper right hand corner of the Matrix view. It is grayed out unless the user has Administrative rights.

The same restrictions on editing a configuration exist just as if the configuration were being edited in graphic mode. It is the responsibility of the Administrative user to follow the following rules while in Editions mode:

- Do not modify the configuration name or dictionary of an existing ProTraq configuration.
- Do not modify the statistical session storage, statistical session name, statistical duration, column content (except for the column filter), column order, or columns (add or delete) if the ProTraq configuration is currently associated.
- Do not modify the keywords of the .fse file.

The following is an example of a configuration in fse file format:

```
SECTION: MAIN
# ProTraq
# Copyright (c) 1998-2004 Steleus S.A.
# DPIMobileActivity, generated Mon Nov 08 14:50:37 CET 2010
# MobileActivityDPI VERSION: 600
DLL: FSEQOS MODE: AFTER
DESTINATION::DPIMobileActivity
ALARMPERIOD: 30
ALARMSERVER::0
STATPERIOD: 60:6048000
COMMENT: MobileActivityDPI POINTCODEFORMAT: 0:0:8:8:8:0
INSTANCE: INSTANCEOID:
SECTION: COLUMN: 0: FIELD: On APN NAME: APN
TOPFIELD: 2
SECTION: COLUMN: 1: CUMULATIVE: Packet uplink
NAME: UP FIELD: UplinkPackets SCALE: 1
FILTER: 0
SECTION: LINE: 0: TOP: 30:0:3
NAME: Service
CRITERIA: Application: 1000:99000
ORDER: 7:1
FILTER: 0
```

Figure 16: fse file format

Filtering the configuration and session listings

To filter the information that displays in the Configuration and Session listings, follow these steps:

- Highlight the configuration from the listing and select the Filter icon.
- Select a filter from the drop down list or build a new filter by entering the following information:

Filter Name	The name of the filter
Description	A description of the filter characteristics

Table 40: Filter Details

- Select the Add button to add a filter condition. Filter conditions are lettered in capitals. For example, the first one is A, second is B, and the third one is C.
- Select a field from the drop down listing.
Note: When you select a field, the field description is available by clicking on the question mark next to the field name.
- Enter an operator. Valid operators are:

<>	Not equal to
<=	Less than or equal to
>=	Greater than or equal to
>	Greater than
=	Equal to
<	Less than

Table 41: Operators

- Enter a value for the filter or select one from the drop down list.
Note:
 - The format supported for IP-V4 is as usual 4 groups in decimal separated by ‘.’ : xxx.xxx.xxx.xxx.
 - The format supported for IP-V6 fields is 8 groups in hexadecimal separated by ‘:’ with canonical way
 xxxx: xxxx: xxxx: xxxx: xxxx: xxxx: xxxx: xxxx
 - It will be possible to use prefixes notation to be able to find range. This will be available for IPV4 and V6.
 For Example: 1082::8:800:200C:417A/11
 Will search all IPs between
 ‘108000000000000000000000000000’ AND
 ‘109FFFFFFFFFFFFFFFFFFFFFFFFFFFFFFFF’
 - In IP-V6, all IP Addresses with 0 in the first 96 bits are considered as V4 and will be displayed as V4 and will never be presented as ::xxx.xxx.xxx.xxx

- To add an additional characteristic, determine the operator (And / Or). Select whether the expression should be enclosed in brackets and select the Add button.
- When you have finished adding filter conditions, select “Save” to save the filter conditions in the All Records drop down list.
- When the filter saves, select Apply. The filter is applied to the listing and the list refreshes.

Importing and exporting files

ProTraq enables you to import pre-defined ProTraq configuration files. It also allows you to export the ProTraq configuration or dependent objects to a file.

Importing a file into ProTraq

Complete the following steps to import a ProTraq Configuration file:

- From the Main page, select File > Import.

The Import ProTraq Configuration screen opens.

- Click the Browse button to search for the File Name of the file to import.
- Enter the protocol name using one of the following methods:
 - Type in any protocol name sequence. ProTraq filters the appropriate entries as you type.
 - Select a protocol using the Select Protocol from button. Select the protocol from either the Sessions tab (which specifies the protocol associated with the session) or the Protocol tab (which specifies an individual protocol). When the protocol is selected, click the Done button.
- After selecting the protocol, click the Next button.
- Select the Is Password Encrypted? checkbox if working with a password encrypted file. Type in the Password, if appropriate.
- Select Windows Configuration.
- Select the Import button to complete the process. The configuration is imported and appears in the ProTraq configuration screen.

Exporting a ProTraq configuration

Follow these steps to export a ProTraq configuration.

- Highlight the configuration and select the Export ProTraq Configuration icon.
- Select to save the file or open it in a program of your choice.
- The ProTraq configuration opens or saves in .fse format.

Exporting dependent objects

ProTraq allows you to export the following dependent objects into a .csv format:

- ProAlarm Map -- uses configuration alarms
- Historical Scenarios -- uses configurations
- ProPerf Dashboards -- uses configuration statistic lines
- Scheduler information

Follow these steps to export dependent objects:

- Highlight the configuration and select the Export Dependent Objects icon.
- Select to save the file or open it in a program of your choice.
- The dependent object listing opens or saves in .csv format.

Chapter 4: Working With ProTraq Results

- **Overview**
- **Principle**
- **Statistics**
- **Alarms**
- **Using the Historical ProTraq application for KPI calculation on historical XDRs**
- **Turning on troubleshooting drilldown for xDR sessions**

ProAlarm Viewer gives you the capability to use the troubleshooting drilldown functionality as an efficient means to diagnose an issue on a telecom network. Before using this functionality, you must activate it using ProTraq.

With this functionality, starting from an alarm on a KPI threshold violation, the user will be able to:

- Drill down to the KPI trend on a chart
- Drill down to the list of KPIs

With this functionality, starting from KPIs sessions, the user will be able to:

- Drill down to the list of xDRs that were used to calculate that KPI, with the protocol decoding associated

Using this drilldown functionality allows the user to easily search the root causes of a failure without needing to know exactly where the problem occurred. Instead, it is possible to simply follow the drill down path from the alarm to the faulty xDRs and error root cause on the network.

Perform the following steps to turn on the troubleshooting drilldown function:

- From the ProTraq Configuration screen, highlight the session for which you need to turn on drilldown.
- Select the Show Details icon.

The bottom half of the screen shows the details for the xDR session.

- Select Apply from that detailed section.
- The troubleshooting drilldown functionality is now active for that xDR session, allowing you to use the drilldown function in ProAlarm Viewer or System Alarms.

Overview

This chapter provides a brief overview of the principles used and statistics created by ProTraq. It also provides information on using the Historical ProTraq application, which allows you to calculate new KPIs on historical xDRs in order to recognize operational trends.

Principle

The Data Server or IXP subsystem produces statistics and alarms based on the KPIs defined in ProTraq configurations.

The statistics are given in the form of either an IXP session or a Data Server session. The alarms appear in the ProAlarm viewer.

Statistics

The statistics session conforms to the start and end times defined during the creation of a ProTraq configuration. Each time a statistics period ends, a set of records is written to the session. Each filter generates a record where N lines are generated for each top selection (where N is the number of results retained in the final classification). Each counter produces one column (record field). A record contains the counters corresponding to one filter in one statistics time period plus this information:

- the end time of the period
- the real period duration (it can be less than the defined statistics time period)
- a sample rate, which is more than one if the Tool was working in degraded mode (due to processing overhead)
- the main filter name (if one has been defined)
- the filter name (or a compound filter name with the field values, for the top selection lines)

Here is an example of the information included in a record. Assume the configuration contains the following:

- 3 filters - "Not answered calls" (selecting the unanswered calls), "Busy calls" (selecting the busy calls), and a top selection "Cause family" dispatching the calls according to their cause family value (other than unanswered and busy)
- 3 counters for the total number of calls - incoming calls, outgoing calls, and a field for the cause family name.
- 1 field holding the cause family field

From this configuration, the statistics are created and display.

Rec No	Period end	Duration	Sample	Corner	Line
1	30/03/2005 12:53:00	12	1	-	Not answered calls
2	30/03/2005 12:53:00	12	1	-	Busy calls
3	30/03/2005 12:53:00	12	1	-	Cause family:1
4	30/03/2005 12:53:00	12	1	-	Cause family:2
5	30/03/2005 12:53:00	12	1	-	Cause family:3
6	30/03/2005 12:53:00	12	1	-	Cause family:4
7	30/03/2005 12:53:00	12	1	-	Cause family:5
8	30/03/2005 12:53:00	12	1	-	Cause family:6
9	30/03/2005 12:53:00	12	1	-	Cause family:7
10	30/03/2005 12:53:00	12	1	-	Cause family:8
11	30/03/2005 12:53:00	12	1	-	Cause family:9
12	30/03/2005 12:53:00	12	1	-	Cause family:10
13	30/03/2005 12:53:00	30	1	-	Not answered calls
14	30/03/2005 12:53:00	30	1	-	Busy calls
15	30/03/2005 12:53:00	30	1	-	Cause family:1
16	30/03/2005 12:53:00	30	1	-	Cause family:2
17	30/03/2005 12:53:00	30	1	-	Cause family:3
18	30/03/2005 12:53:00	30	1	-	Cause family:4
19	30/03/2005 12:53:00	30	1	-	Cause family:5
20	30/03/2005 12:53:00	30	1	-	Cause family:6

#	Total calls	Incoming calls	Outgoing calls	Cause family name
202	74	63	11	SST send special tone information
0	0	3	0	CCC circuit group congestion
14	14	5	9	IFL ISDN call failure
13	13	5	8	Other
12	12	13	0	HE Hang up during establishment
11	11	4	7	SSB subscriber busy
10	10	4	6	ACB access barred
9	10	6	4	UNN unallocated number
8	10	5	5	CFL call failure
7	10	7	3	NA no answer
6	10	5	5	LOS line out of service
5	10	5	5	Normal clearing
4	167	172	0	CFL call failure
3	300	23	277	CCC circuit group congestion
2	300	23	277	NA no answer
1	29	20	9	SSB subscriber busy
0	29	20	9	MPR misdialed trunk prefix
0	29	20	9	Other
0	29	20	9	CCC circuit group congestion
0	29	20	9	Normal clearing

Figure 17: Statistics

You must first log into the Network Software Platform (NSP) that uses the ANSI-ISUP protocol. To log into NSP navigate to NSP using your Web browser, and then log in using your NSP userid and password.

Alarms

Alarm events are sent to the management platform through the agent. Each time an alarm period ends, captured events can be sent to the management platform. Each event is attached to one statistic counter.

An event can be:

- a major alarm due to a counter overflow (or underflow), in comparison with a high threshold, that appeared in the current alarm period
- a minor alarm due to a counter overflow (or underflow), in comparison with a low threshold, that appeared in the current alarm period
- a clearing of an alarm because all overflow or underflow conditions disappeared in the current alarm period

The following information is also transmitted with each event:

- session name, line number and reference, column number
- event severity (major, minor, clear)
- threshold value, counter value

Using the Historical ProTraq application for KPI calculation on historical XDRs

Calculating new Key Performance Indicators (KPIs) on historical xDRs allows you to recognize abnormal traffic conditions through the generated alarms. ProTraq’s ability to calculate and store xDRs while the system is in operation provides you with an advantage in recognizing trends.

Access to these stored xDRs is available by using the Historical ProTraq application. This application is available in the Configuration section on the main PIC application listing screen.

The ability to calculate KPIs on historically stored xDRs can be used in the following scenarios:

- Historically stored xDRs can help troubleshoot in order to fine-tune the KPI calculation. For instance, if there is a failure in the network but none of the KPIs generated an alarm, you can replay the xDRs around the failure time and update the existing KPI (or create a new one). In this scenario, the same failure will now produce an alarm.
- If the KPIs for a period of time are missing or are partial, you can recalculate the missing KPIs.
- For older KPIs, it may be necessary to reduce the granularity, which can be scheduled to occur automatically. For example, each day you can aggregate the KPIs that are one week old to change the granularity from 5 min to 1 hour.

Note: Since calculation of partial KPIs is not available, ProTraq suspends the calculation of KPIs if one of the sources becomes inactive. To ensure accurate reporting, all input streams should be set to Critical and be active and on-time.

Perform the following steps to calculate new KPIs on historical xDRs:

- Select Historical ProTraq from the main PIC application listing screen. Historical ProTraq is listed under Configuration applications.

The Historical ProTraq application opens.

- Select the Add Record icon.

The Historical KPI parameters screen opens.




Figure 18: Historical KPI parameters screen

- Enter a scenario name and select whether you want ProTraq to purge the selected period before generating new KPIs.
- Select Next.

The Historical KPI Protraq config screen opens.



Figure 19: Historical KPI Protraq config screen

- Select the configuration to use from the list.
- Select Next.

The Historical KPI Input screen opens.




Figure 20: Historical KPI Input screen

- Select the input session to use from the list.
- Select Next.

The Historical KPI Query screen opens.



Figure 21: Historical KPI Query screen

- Select the query to use from the list.
- Select Next.

The Historical KPI Output session screen opens.



Figure 22: Historical KPI Output session

- Enter a name for the output session or select to use an existing output session.
- Select Next.

The Historical KPI Scheduler screen opens.




Figure 23: Historical KPI Scheduler screen

- Select to activate the schedule using the checkbox. Fill in the appropriate schedule information.
- Select Next.

The Historical KPI Summary screen opens.



Figure 24: Historical KPI Summary screen

- Check to confirm that all the information for the scenario is correct.
- Select Finish.

ProTraq saves the scenario and returns you to the Scenario screen.

- To run the KPI calculations on historical xDRs, highlight the scenario and select the Run icon. The Query Settings window opens and allows you to select the First selected date and time, and Second selected date and time for the scenario.




Figure 25: Query Setting Screen

- After choosing the First and Second date and time, select Apply to run the scenario. While the scenario is running, you can get updated processing information by hovering your mouse over the Status section (which shows Begin date and End date) and the Current Progress section (which shows the percentage of the scenario processed, the number of xDRs processed and the number of KPIs processed).

Note: It is important to take note of privacy settings related to historical scenarios. To allow other users to view a scenario, all four components (the scenario, the configuration, the input session and the output session) must be set with READ permission. To allow other users to edit or start/stop a scenario, all four components must be set with a WRITE/EXECUTE permission.

Note: If you have scheduled to run historical KPI information for 30 days, your session may experience a crash. If the procedure crashes, the session will not be recovered but will be finished with FAILED state. To recover a session from a failed state either rerun the same scenario with the purge parameter set to ON, which will delete already created KPIs, or check the ProTraq/ProScan time tag of the last created KPI and create a new scenario for the remaining period.

Turning on troubleshooting drilldown for xDR sessions

ProAlarm Viewer gives you the capability to use the troubleshooting drilldown functionality as an

efficient means to diagnose an issue on a telecom network. Before using this functionality, you must activate it using ProTraq.

With this functionality, starting from an alarm on a KPI threshold violation, the user will be able to:

- Drill down to the KPI trend on a chart
- Drill down to the list of KPIs

With this functionality, starting from KPIs sessions, the user will be able to:

- Drill down to the list of xDRs that were used to calculate that KPI, with the protocol decoding associated

Using this drilldown functionality allows the user to easily search the root causes of a failure without needing to know exactly where the problem occurred. Instead, it is possible to simply follow the drill down path from the alarm to the faulty xDRs and error root cause on the network.

Perform the following steps to turn on the troubleshooting drilldown function:

- From the ProTraq Configuration screen, highlight the session for which you need to turn on drilldown.
- Select the Show Details icon.

The bottom half of the screen shows the details for the xDR session.

- Select Apply from that detailed section.
- The troubleshooting drilldown functionality is now active for that xDR session, allowing you to use the drilldown function in ProAlarm Viewer or System Alarms.

Chapter 5: Defining and Modifying Flavor (PC Format) of Session

- Define Flavor (PC Format) of Session
- **Modifying flavor of a xDR Session**

Define Flavor (PC Format) of Session

Flavor associated with session can be defined in CCM by one of following scenarios:

- Defining flavor while creating session through xDR Data Flow Assistant
- Defining flavor while adding session
- Defining flavor while defining store DFP

Defining flavor while creating session through xDR DataFlow Assistant

- Login to CCM application
- Go to Mediation->Sites->Site->IXP->Server->DataFlowProcessings
- Define DFP by selecting “xDR DataFlow Assistant” in right click menu.
- Wizard will also ask for flavor if underlying protocol has point code fields.

Mediation > Sites > IXP G6 75 > IXP > IXP0075 > Dataflow Processings > xDR Dataflow Assistant

Step 4: Configure Session(s)



#	xDR Builder Name	Session Name	Life Time(hours)	Point Code Flavor
1	SS7 BICC ETSI CDR reconstitution	sdgeg	72	DEFAULT ANSI ETSI_I ETSI_N CHINESE JAPANESE

Figure 26: Associate flavor while creating session through xDR Data Flow Assistant

Defining flavor while adding Session through session list

- Login to CCM application
- Click on xDR Sessions. This will display of list of sessions
- Click on Add Button on toolbar.
- The wizard will ask for Point Code Flavor only when the dictionary has point code type field. In this case, select the flavor for the session from drop down.

Session Name	Lifetime (hours)
test	72
Storage	Point Code Flavor
ixp0075_Pool	DEFAULT
Dictionary	SS7 AIN TDR_7.1
Description	

Point Code Flavor dropdown options: DEFAULT, ANSI, ETSI_I, ETSI_N, CHINESE, JAPANESE

Figure 27: Associating flavor with Session

Defining flavor while defining store DFP

- Login to CCM application
 - Go to Mediation->Sites->Site->IXP->Server->Data Flow Processings
 - Select “Add” in right click menu and define store DFP
 - Define flavor in wizard where it asks for create session
- Note:** The flavor dropdown will come only if underlying protocol has point code fields.

Modifying flavor of a xDR Session

To modify PC Format of a session, follow the following steps

- Login to CCM application
 - Click on xDR Sessions. This will display of list of sessions.
 - Click on Modify Button on toolbar.
 - Change the flavor for the session by selecting new flavor in drop down and Click OK.
- Note:** The flavor dropdown will come only if underlying protocol has point code fields.