

**Oracle® Communications
Diameter Signaling Router**
IDIH Alarm Forwarding Administrator's Guide
E56004 Revision 1

July 2014

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information on content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

Table of Contents

Chapter 1: Introduction.....	6
Overview.....	7
Scope and Audience.....	7
Manual Organization.....	7
Related Publications.....	7
My Oracle Support (MOS).....	7
Emergency Response.....	8
Locate Product Documentation on the Oracle Technology Network Site.....	8
Chapter 2: Introduction to Alarm Forwarding.....	9
Overview.....	10
Setting User Preferences on IDIH Dashboard.....	10
Alarm Forwarding Key Features.....	11
Alarm Forwarding Architecture.....	11
Chapter 3: Working in Alarm Forwarding.....	13
Accessing Alarm Forwarding.....	14
Alarm Forwarding Toolbar.....	14
Using Alarm Forwarding.....	14
Creating a Filter.....	15
Editing a Filter.....	16
Alarm Forwarding Test Connection.....	16
Test Connection for SMTP.....	16
Test Connection for SNMP.....	17
Chapter 4: SNMP Agent.....	18
SNMP Overview.....	19
Alarm Forwarding MIB.....	19

List of Figures

Figure 1: Alarm Forwarding Toolbar.....	14
Figure 2:	15
Figure 3: Connection Test Dialog.....	16

List of Tables

Table 1: Alarm Forwarding Toolbar Icons.....	14
--	----

Chapter 1

Introduction

Topics:

- *Overview.....7*
- *Scope and Audience.....7*
- *Manual Organization.....7*
- *Related Publications.....7*
- *My Oracle Support (MOS).....7*
- *Emergency Response.....8*
- *Locate Product Documentation on the Oracle Technology Network Site.....8*

This section contains an overview of the available information for the Integrated Diameter Intelligence Hub.

The contents include sections on the organization, scope, and audience of the documentation, as well as how to receive customer support assistance.

Overview

This documentation provides information about the functions of the Alarm Forwarding application of the Integrated Diameter Intelligence Hub (IDIH).

Note: The Alarm Forwarding application is only available to users logging into IDIH as "idihadmin."

Scope and Audience

This user's guide provides information about the Alarm Forwarding application. This guide provides definitions and instructions to help the user efficiently and effectively define conditions and destinations for forwarding Alarms.

Manual Organization

Introduction contains general information about this document, how to contact *My Oracle Support (MOS)*, and *Locate Product Documentation on the Oracle Technology Network Site*.

Introduction to Alarm Forwarding provides an introduction to the Alarm Forwarding application.

Working in Alarm Forwarding contains information about procedures used while using the Alarm Forwarding application.

SNMP Agent contains information about the SNMP Agent of the Alarm Forwarding application.

Related Publications

For information about additional publications that are related to this document, refer to the *Related Publications Reference* document, which is published as a separate document on the Oracle Technology Network (OTN) site. See *Locate Product Documentation on the Oracle Technology Network Site* for more information.

My Oracle Support (MOS)

MOS (<https://support.oracle.com>) is your initial point of contact for all product support and training needs. A representative at Customer Access Support (CAS) can assist you with MOS registration.

Call the CAS main number at **1-800-223-1711** (toll-free in the US), or call the Oracle Support hotline for your local country from the list at <http://www.oracle.com/us/support/contact/index.html>. When calling, make the selections in the sequence shown below on the Support telephone menu:

1. Select **2** for New Service Request
2. Select **3** for Hardware, Networking and Solaris Operating System Support
3. Select **2** for Non-technical issue

You will be connected to a live agent who can assist you with MOS registration and provide Support Identifiers. Simply mention you are a Tekelec Customer new to MOS.

MOS is available 24 hours a day, 7 days a week, 365 days a year.

Emergency Response

In the event of a critical service situation, emergency response is offered by the Customer Access Support (CAS) main number at **1-800-223-1711** (toll-free in the US), or by calling the Oracle Support hotline for your local country from the list at <http://www.oracle.com/us/support/contact/index.html>. The emergency response provides immediate coverage, automatic escalation, and other features to ensure that the critical situation is resolved as rapidly as possible.

A critical situation is defined as a problem with the installed equipment that severely affects service, traffic, or maintenance capabilities, and requires immediate corrective action. Critical situations affect service and/or system operation resulting in one or several of these situations:

- A total system failure that results in loss of all transaction processing capability
- Significant reduction in system capacity or traffic handling capability
- Loss of the system's ability to perform automatic system reconfiguration
- Inability to restart a processor or the system
- Corruption of system databases that requires service affecting corrective actions
- Loss of access for maintenance or recovery operations
- Loss of the system ability to provide any required critical or major trouble notification

Any other problem severely affecting service, capacity/traffic, billing, and maintenance capabilities may be defined as critical by prior discussion and agreement with Oracle.

Locate Product Documentation on the Oracle Technology Network Site

Oracle customer documentation is available on the web at the Oracle Technology Network (OTN) site, <http://docs.oracle.com>. You do not have to register to access these documents. Viewing these files requires Adobe Acrobat Reader, which can be downloaded at www.adobe.com.

1. Log into the Oracle Technology Network site at <http://docs.oracle.com>.
2. Under **Applications**, click the link for **Communications**.
The **Oracle Communications Documentation** window opens with Tekelec shown near the top.
3. Click **Oracle Communications Documentation for Tekelec Products**.
4. Navigate to your Product and then the Release Number, and click the **View** link (the **Download** link will retrieve the entire documentation set).
5. To download a file to your location, right-click the PDF link and select **Save Target As**.

Chapter 2

Introduction to Alarm Forwarding

Topics:

- *Overview.....10*
- *Alarm Forwarding Key Features.....11*
- *Alarm Forwarding Architecture.....11*

This chapter provides basic information about the Alarm Forwarding application.

Overview

Alarm Forwarding enables the user to forward alarms to specified destinations. The user can create alarm forwarding rules using Filters.

This application handles several types of alarms, including those pertaining to

- Traffic supervision
- Quality of service
- System errors

Setting User Preferences on IDIH Dashboard

Once inside IDIH, a user can set User Preferences. These include:

- Time specifications (date format, time zone, etc.)
- Enumeration values (numerals vs. text)

Setting Time Format

Follow these steps to set the time format:

1. Click **User Preferences** on the Application board.
The User Preferences screen is displayed.
2. Click the **Date/Time** tab.
The Date/Time screen is displayed. The red asterisk denotes a required field.
Note: Use the tips on the screen to help configure the time format.
3. Enter the format for these time-related displays.
 - **Date format**
 - **Time format**
 - **Date and time fields**
4. Select the formats for these time-related displays by using the drop-down arrow.
 - **Duration fields** - how the hours, minutes, seconds, and milliseconds of the Time format is displayed
 - **Time zone**
Note: The local time zone must be chosen to get local time.
5. To reset the time-related displays to default settings, click **Reset**.
6. Click **Apply** to save settings.

Setting Mapping Preferences

The user can set the Mapping settings using the User Preferences feature.

Follow these steps to set Mapping preferences.

1. Click **User Preferences** in the Application board.
The User Preferences screen is displayed.
2. Click the **Mapping** tab.
The Mapping screen is displayed.
3. Check **Translate ENUM values** to display text instead of numerals.
Enumeration is used by TDRs to display text values instead of numeric. Rather than showing the numeral for Alarm Severity, the user interface will show the actual word, such as "Major" or "Critical."
4. Check **IP Address to Node Name** to translate an IP Address to a textual Node Name.
5. To reset the Mapping values to the default, click **Reset**.
6. Click **Apply** to save the changes.

Alarm Forwarding Key Features

The key features of Alarm Forwarding include

- A Simple Network Management Protocol (SNMP) agent compliant with ITU x721, X733
- Acknowledge / Terminate capability from SNMP
- For an alarm event, only one email is sent to a selective list of email addresses. Alarm Forwarding allows a list of email addresses to be attached to a filter. It is possible to send a particular type of alarm to a list of email addresses and another type of alarm to a different list of email addresses. These multiple email address are set when Creating a Filter and Editing a Filter.

Each alarm is evaluated against each filter. The same alarm can pass different filter conditions and be sent to different destinations. If the same alarm passes different filters and is forwarded using SNMP in each of those filters, the alarm is sent only once since Alarm Forwarding detects this condition and SNMP has only one destination.

Also see [Alarm Forwarding MIB](#).

Alarm Forwarding Architecture

Alarm Forwarding supports the forwarding of alarms to applications in an external system. It supports the following two protocols for alarm forwarding:

- Traps (SNMP)
- Mails (SMTP)

Alarm Forwarding supports the use of Filters. You can create, edit, and delete a Filter and a forwarding destination. A Filter List provides the following information for a Filter:

- Rec No - record number; a number given for indexing alarms in the Filter alarm list
- Rule - unique system-generated number that identifies the Filter
- Filter Name - name of the Filter
- Description - description of the Filter
- Destination Name - destination of the filtered alarm. It can be SNMP or SMTP or both.

You can set the forwarding criteria based on the Filters defined for the following fields:

- Ack State
- Alarm Cleared User
- Alarm ID
- Alarm Type
- Managed Object Class
- Managed Object ID
- Perceived Severity ID
- Probable Cause
- Specific Problem
- User Name

Note: Destination configuration is part of platform configuration. These steps (SMTP server, SNMP version, and target IP) are described in *IDIH Installation Document*.

Chapter 3

Working in Alarm Forwarding

Topics:

- *Accessing Alarm Forwarding.....14*
- *Alarm Forwarding Toolbar.....14*
- *Using Alarm Forwarding.....14*
- *Alarm Forwarding Test Connection.....16*

This chapter provides information about procedures used when working in the Alarm Forwarding application.

Accessing Alarm Forwarding

To open Alarm Forwarding, follow these steps:

1. Log in to IDIH .
The IDIH Application board is displayed.
2. Click **Alarm Forwarding**.
The Alarm Forwarding home page is displayed.

Alarm Forwarding Toolbar



Figure 1: Alarm Forwarding Toolbar

Table 1: Alarm Forwarding Toolbar Icons

Button	Explanation
Select Columns	Allows the user to select which columns are displayed
Navigation Arrows	Moves back and forth among the records.
Filters	Number of records to display on a page
Set Size	Sets the number of records to display per page
Refresh	Resets display to include the most current data
Add Filter	Adds a Filter, defining the types of alarms to be forwarded and their destination
Modify Filter	Edits an existing filter's definition
Delete Filter	Deletes a selected filter
Test Connection	Sends a test message to the destination SNMP and/or SMTP

Using Alarm Forwarding

This section explains how to set conditions and destinations for forwarding alarms.

Creating a Filter

Filters define the types of alarms to be forwarded and their destination. Filters return True or False results depending upon whether the alarm should be forwarded or not. Each Filter that returns True is forwarded to its specified destination.




Figure 2:

To create a Filter,

1. Click the **Add Filter** icon on the toolbar.
The Create New Filter dialog is displayed.
2. Type in a **Filter Name** and **Description**.
3. Select Filter and click the **Add** icon.
4. Select a Field, Operator, and Value from the drop-down menus.
5. Enter an Expression.
6. Select **Next** to advance to the Destination display.
7. Select SNMP and/or SMTP.
8. Enter Email list (addresses) information.
Note: Email list is only used when SMTP is selected.
9. To advance to the Filter Creation Dialog Summary display, select **Next**.
10. If the information on the Summary display is correct, select finish create this filter. If there are errors in this summary information, select the previous to return to the display to correct the errors.

11. To add another filter, repeat from [Step 1](#).

Editing a Filter

To edit an existing Filter:

1. Select a Filter from the Filter table.
2. Click the **Modify Filter** icon on the toolbar.
The Filter Creation Dialog is displayed.
3. Modify the appropriate field(s) as needed.
For specific information on fields and options, see [Creating a Filter](#).
4. Click **Next**.
The Select Forwarding Destination dialog is displayed.
5. Update Destination information as necessary.

Note: For SNMP, only one trap destination can be defined. For SMTP, multiple email destinations are permitted.

6. Click **Finish** to save the record changes.

Alarm Forwarding Test Connection

The user can send a test message to the destination SNMP and/or SMTP using the **Connection Test Dialog** screen after clicking the **Test Connection** icon.



Figure 3: Connection Test Dialog

Test Connection for SMTP

The configuring user should verify the SMTP address, SMTP availability thru firewalls, and SMTP access mode. Secured destinations require additional parameters be defined and are described in the Installation Document.

1. If the message was received in the targeted mail box, the test was successful. This procedure is complete.
If the message is not in the targeted mail box, continue with this procedure.
2. Use the Audit Viewer application to verify if a mail sending error is logged.
3. Contact the [My Oracle Support \(MOS\)](#) to investigate and help determine the correct SMTP configuration.

Test Connection for SNMP

The configuring user should verify the SNMP address and the SNMP availability thru firewalls. Secured destinations require additional parameters be defined and are described in the *IDIH Installation Document*.

1. Verify the test trap was received by the management system. If the test trap was received by the management system, the test was successful. This procedure is complete.
If the test trap was not received by the management system, continue with this procedure.
2. Contact the [My Oracle Support \(MOS\)](#) to investigate and help determine the correct SNMP configuration.

Chapter 4

SNMP Agent

Topics:

- *SNMP Overview.....19*
- *Alarm Forwarding MIB.....19*

This chapter provides information about how the SNMP Agent functions in the Alarm Forwarding application.

SNMP Overview

The main features of the Simple Network Management Protocol (SNMP) agent of Alarm Forwarding are:

Overview

- The Management Information Base (MIB) contains Managed Object types, Managed Objects, and opened alarms in specific tables.
- The MIB is loaded at SNMP agent startup with metadata and opened alarms already forwarded.

Validation of Traps Sent

- Traps contain a sequence number (since agent startup) that permits Telecommunications Management Network (TMN) to check that none were lost.
- In case of a gap (lost trap) or if the number is lower, the process is restarted and TMN can re-synchronize its database by querying the opened alarms table.

Acknowledgment or Termination from SNMP

A dedicated Access Module for HP TeMIP is available to integrate easily with the NSP Forwarding SNMP agent.

Note: SNMP trap forwarding requires the system administrator to configure the destination address, please refer to section "Configure SNMP Management Server" in the IDIH Installation Document.

Alarm Forwarding MIB

Shown here is the Alarm Forwarding MIB , which is located on the NSP server at

```
/usr/TKLC/xIH/apps/forwarding/target/misc/NSP-FORWARDING-MIB

-- File Name : NSP-FORWARDING-MIB
-- Date      : Mon Nov 21 10:18:28 CET 2006
-- Author    : AdventNet Agent Toolkit Java Edition - MIB Editor 6

NSP-FORWARDING-MIB DEFINITIONS ::= BEGIN
  IMPORTS
    RowStatus, DisplayString
      FROM SNMPv2-TC
    NOTIFICATION-GROUP, OBJECT-GROUP
      FROM SNMPv2-CONF
    enterprises, MODULE-IDENTITY, OBJECT-TYPE, Integer32,
  NOTIFICATION-TYPE
      FROM SNMPv2-SMI;
  steleus MODULE-IDENTITY
```

```

LAST-UPDATED      "200602131148Z"
ORGANIZATION     "Tekelec"
CONTACT-INFO     "ttprocessing@tekelec.com"
DESCRIPTION       "Description"
REVISION         "200602131148Z"
DESCRIPTION       "NSP module"
 ::= { enterprises 4404 }

nsp      OBJECT IDENTIFIER
 ::= { steleus 8 }

forwarding      OBJECT IDENTIFIER
 ::= { nsp 6 }

nspManagedObjectClassTable      OBJECT-TYPE
 SYNTAX      SEQUENCE OF NspManagedObjectClassEntry
 MAX-ACCESS  not-accessible
 STATUS      current
 DESCRIPTION  "NSP managed object class table"
 ::= { forwarding 1 }

nspManagedObjectClassEntry      OBJECT-TYPE
 SYNTAX      NspManagedObjectClassEntry
 MAX-ACCESS  not-accessible
 STATUS      current
 DESCRIPTION  "NSP managed object class entry"
 INDEX      { nspManagedObjectClassId }
 ::= { nspManagedObjectClassTable 1 }

NspManagedObjectClassEntry ::= SEQUENCE {
    nspManagedObjectClassId Integer32,
    nspManagedObjectClassName DisplayString,
    nspManagedObjectClassDescription DisplayString,
    nspManagedObjectClassRowStatus RowStatus
}

nspManagedObjectClassId OBJECT-TYPE
 SYNTAX      Integer32 ( -2147483648 .. 2147483647
)
 MAX-ACCESS  read-only
 STATUS      current
 DESCRIPTION  "Value that defines an instance of managed
object class in the table"
 ::= { nspManagedObjectClassEntry 1 }

nspManagedObjectClassName      OBJECT-TYPE
 SYNTAX      DisplayString
 MAX-ACCESS  read-only
 STATUS      current
 DESCRIPTION  "NSP managed object class instance name"
 ::= { nspManagedObjectClassEntry 2 }

nspManagedObjectClassDescription      OBJECT-TYPE
 SYNTAX      DisplayString
 MAX-ACCESS  read-only
 STATUS      current
 DESCRIPTION  "NSP managed object class instance

```

```

description"
      ::= { nspManagedObjectClassEntry 3 }

nspManagedObjectClassRowStatus   OBJECT-TYPE
      SYNTAX          RowStatus { active ( 1 ) , notInService
( 2 ) , notReady ( 3 ) , createAndGo ( 4 ) , createAndWait ( 5 ) , destroy ( 6
) }

      MAX-ACCESS      read-create
      STATUS          current
      DESCRIPTION     "SMI v2 required attribute"
      ::= { nspManagedObjectClassEntry 50 }

nspManagedObjectTable   OBJECT-TYPE
      SYNTAX          SEQUENCE OF NspManagedObjectEntry
      MAX-ACCESS      not-accessible
      STATUS          current
      DESCRIPTION     "Description"
      ::= { forwarding 2 }

nspManagedObjectEntry   OBJECT-TYPE
      SYNTAX          NspManagedObjectEntry
      MAX-ACCESS      not-accessible
      STATUS          current
      DESCRIPTION     "Row Description"
      INDEX           { nspManagedObjectId}
      ::= { nspManagedObjectTable 1 }

NspManagedObjectEntry ::= SEQUENCE {
      nspManagedObjectId Integer32,
      nspManagedObjectName DisplayString,
      nspManagedObjectClassIdRef Integer32,
      nspManagedObjectParent Integer32,
      nspManagedObjectRowStatus RowStatus
}

nspManagedObjectId   OBJECT-TYPE
      SYNTAX          Integer32 ( -2147483648 .. 2147483647
)
      MAX-ACCESS      read-only
      STATUS          current
      DESCRIPTION     "Value that defines an instance of managed
object in the table"
      ::= { nspManagedObjectEntry 1 }

nspManagedObjectName   OBJECT-TYPE
      SYNTAX          DisplayString
      MAX-ACCESS      read-only
      STATUS          current
      DESCRIPTION     "Column Description"
      ::= { nspManagedObjectEntry 2 }

nspManagedObjectClassIdRef   OBJECT-TYPE
      SYNTAX          Integer32 ( -2147483648 .. 2147483647
)
      MAX-ACCESS      read-only

```

```

        STATUS          current
        DESCRIPTION    "Value that defines an instance of managed
object class"
        ::= { nspManagedObjectEntry 10 }

nspManagedObjectParent  OBJECT-TYPE
        SYNTAX          Integer32
        MAX-ACCESS     read-only
        STATUS          current
        DESCRIPTION    "Value that defines an instance of parent
managed object"
        ::= { nspManagedObjectEntry 20 }

nspManagedObjectRowStatus  OBJECT-TYPE
        SYNTAX          RowStatus
        MAX-ACCESS     read-create
        STATUS          current
        DESCRIPTION    "SMI v2 required attribute"
        ::= { nspManagedObjectEntry 50 }

nspAlarmsTable  OBJECT-TYPE
        SYNTAX          SEQUENCE OF NspAlarmsEntry
        MAX-ACCESS     not-accessible
        STATUS          current
        DESCRIPTION    "NSP forwarded opened alarms table"
        ::= { forwarding 3 }

nspAlarmsEntry  OBJECT-TYPE
        SYNTAX          NspAlarmsEntry
        MAX-ACCESS     not-accessible
        STATUS          current
        DESCRIPTION    "NSP forwarded opened alarms entry"
        INDEX          { nspAlarmId }
        ::= { nspAlarmsTable 1 }

NspAlarmsEntry ::= SEQUENCE {
        nspManagedObjectIdRef  Integer32,
        nspAlarmId  Integer32,
        nspAlarmRowStatus  RowStatus,
        nspManagedObjectDN  DisplayString,
        nspAlarmLastEventTime  DisplayString,
        nspAlarmEventType  INTEGER,
        nspAlarmProbableCause  INTEGER,
        nspAlarmPerceivedSeverity  INTEGER,
        nspAlarmTrendIndication  INTEGER,
        nspAlarmThresholdLevel  DisplayString,
        nspAlarmObservedValue  DisplayString,
        nspAlarmAdditionalText  DisplayString,
        nspAlarmSpecificProblem  DisplayString,
        nspAlarmFirstDate  OCTET STRING,
        nspAlarmClearDate  OCTET STRING,
        nspAlarmCriticalCount  Integer32,
        nspAlarmMajorCount  Integer32,
        nspAlarmMinorCount  Integer32,
        nspAlarmWarningCount  Integer32,
        nspAlarmAcknowledged  INTEGER
    }

```

```

nspManagedObjectIdRef      OBJECT-TYPE
    SYNTAX          Integer32 ( -2147483648 .. 2147483647
)
    MAX-ACCESS      read-only
    STATUS          current
    DESCRIPTION     "Value that refers to managed object
involved in the forwarded alarm"
    ::= { nspAlarmsEntry 1 }

nspAlarmId      OBJECT-TYPE
    SYNTAX          Integer32 ( -2147483648 .. 2147483647
)
    MAX-ACCESS      read-only
    STATUS          current
    DESCRIPTION     "Value that defines an instance of
forwarded alarm"
    ::= { nspAlarmsEntry 2 }

nspAlarmRowStatus      OBJECT-TYPE
    SYNTAX          RowStatus { active ( 1 ) , notInService
( 2 ) , notReady ( 3 ) , createAndGo ( 4 ) , createAndWait ( 5 ) , destroy ( 6
) }
    MAX-ACCESS      read-create
    STATUS          current
    DESCRIPTION     "SMI v2 required attribute"
    ::= { nspAlarmsEntry 50 }

nspManagedObjectDN      OBJECT-TYPE
    SYNTAX          DisplayString
    MAX-ACCESS      read-only
    STATUS          current
    DESCRIPTION     "Distinguished name that refers to managed
object involved in the forwarded alarm"
    ::= { nspAlarmsEntry 100 }

nspAlarmLastEventTime      OBJECT-TYPE
    SYNTAX          DisplayString
    MAX-ACCESS      read-only
    STATUS          current
    DESCRIPTION     "Last event time in ASN.1 format
for the last event of the NSP forwarded alarm on
the managed object"
    ::= { nspAlarmsEntry 1000 }

nspAlarmProbableCause      OBJECT-TYPE
    SYNTAX          INTEGER { adapterError ( 1 ) ,
applicationSubsystemFailure ( 2 ) , bandwidthReduced ( 3 ) , callEstablishmentError
( 4 ) , communicationsProtocolError ( 5 ) , communicationsSubsystemFailure ( 6
) , configurationOrCustomizationError ( 7 ) , congestion ( 8 ) , corruptData ( 9
) , cpuCyclesLimitExceeded ( 10 ) , dataSetOrModemError ( 11 ) , degradedSignal
( 12 ) , dteDceInterfaceError ( 13 ) , enclosureDoorOpen ( 14 ) ,
equipmentMalfunction ( 15 ) , excessiveVibration ( 16 ) , fileError ( 17 ) ,
fireDetected ( 18 ) , floodDetected ( 19 ) , framingError ( 20 ) ,
heatingVentCoolingSystemProblem ( 21 ) , humidityUnacceptable ( 22 ) ,

```

```

inputOutputDeviceError ( 23 ) , inputDeviceError ( 24 ) , lanError ( 25 ) ,
leakDetected ( 26 ) , localNodeTransmissionError ( 27 ) , lossOfFrame ( 28 ) ,
lossOfSignal ( 29 ) , materialSupplyExhausted ( 30 ) , multiplexerproblem ( 31 )
, outOfMemory ( 32 ) , ouputDeviceError ( 33 ) , performanceDegraded ( 34 ) ,
powerproblem ( 35 ) , pressureUnacceptable ( 36 ) , processorproblem ( 37 ) ,
pumpFailure ( 38 ) , queueSizeExceeded ( 39 ) , receiveFailure ( 40 ) ,
receiverFailure ( 41 ) , remoteNodeTransmissionError ( 42 ) ,
resourceAtOrNearingCapacity ( 43 ) , responseTimeExcessive ( 44 ) ,
retransmissionRateExcessive ( 45 ) , softwareError ( 46 ) ,
softwareprogramAbnormallyTerminated ( 47 ) , softwareprogramError ( 48 ) ,
storageCapacityproblem ( 49 ) , temperatureUnacceptable ( 50 ) , thresholdCrossed
( 51 ) , timingproblem ( 52 ) , toxicLeakDetected ( 53 ) , transmitFailure ( 54 )
, transmitterFailure ( 55 ) , underlyingResourceUnavailable ( 56 ) ,
versionMismatch ( 57 ) , authenticationFailure ( 58 ) , breachOfConfidentiality
( 59 ) , cableTamper ( 60 ) , delayedInformation ( 61 ) , denialOfService ( 62 )
, duplicateInformation ( 63 ) , informationMissing ( 64 ) ,
informationModificationDetected ( 65 ) , informationOutOfSequence ( 66 ) ,
intrusionDetection ( 67 ) , keyExpired ( 68 ) , nonRepudiationFailure ( 69 ) ,
outOfHoursActivity ( 70 ) , outOfService ( 71 ) , proceduralError ( 72 ) ,
unauthorizedAccessAttempt ( 73 ) , unexpectedInformation ( 74 ) }

MAX-ACCESS           read-only
STATUS               current
DESCRIPTION          "Represents the probable cause values for
the alarms as per [X.721], [X.733] and [X.736]

for the NSP forwarded alarm on the managed object"

 ::= { nspAlarmsEntry 1001 }

nspAlarmPerceivedSeverity   OBJECT-TYPE
SYNTAX          INTEGER { indeterminate ( 0 ) , critical
( 1 ) , major ( 2 ) , minor ( 3 ) , warning ( 4 ) , cleared ( 5 ) }

MAX-ACCESS           read-write
STATUS               current
DESCRIPTION          "Represents the perceived severity values
for the alarms as per [X.733] and [X.721]

for the NSP forwarded alarm on the managed object"

 ::= { nspAlarmsEntry 1002 }

nspAlarmTrendIndication OBJECT-TYPE
SYNTAX          INTEGER { lessSevere ( 0 ) , noChange ( 1 ) ,
moreSevere ( 2 ) }

MAX-ACCESS           read-only
STATUS               current
DESCRIPTION          "Represents the trend indication values
for the alarms as per [X.733]

for the NSP forwarded alarm on the managed object"

 ::= { nspAlarmsEntry 1003 }

nspAlarmThresholdLevel   OBJECT-TYPE
SYNTAX          DisplayString
MAX-ACCESS           read-only
STATUS               current

```

```

        DESCRIPTION      "Represents the threshold level indication
values (real) for the alarms as per [X.733]
                                         for the last event of the NSP forwarded alarm on
the managed object"
        ::= { nspAlarmsEntry 1004 }

nspAlarmObservedValue   OBJECT-TYPE
        SYNTAX          DisplayString
        MAX-ACCESS      read-only
        STATUS          current
        DESCRIPTION     "Represents the threshold observed values
(real) for the alarms as per [X.733]
                                         for the last event of the NSP forwarded alarm on
the managed object"
        ::= { nspAlarmsEntry 1005 }

nspAlarmAdditionalText  OBJECT-TYPE
        SYNTAX          DisplayString
        MAX-ACCESS      read-only
        STATUS          current
        DESCRIPTION     "Represents the additional text field for
the alarm as per [X.733]
                                         for the last event of the NSP forwarded alarm on
the managed object"
        ::= { nspAlarmsEntry 1006 }

nspAlarmEventType        OBJECT-TYPE
        SYNTAX          INTEGER { otherAlarm ( 1 ) ,
communicationAlarm ( 2 ) , environmentalAlarm ( 3 ) , equipmentAlarm ( 4 ) ,
integrityViolation ( 5 ) , processingErrorAlarm ( 10 ) , qualityOfServiceAlarm ( 11 ) }
        MAX-ACCESS      read-only
        STATUS          current
        DESCRIPTION     "Represents the ITU event type value for
the alarms as per [X.721], [X.733] and [X.736]
                                         for the NSP forwarded alarm on the managed object"
        ::= { nspAlarmsEntry 1007 }

nspAlarmSpecificProblem  OBJECT-TYPE
        SYNTAX          DisplayString
        MAX-ACCESS      read-only
        STATUS          current
        DESCRIPTION     "Represents the specific problem name
for the NSP forwarded alarm on the managed object"
        ::= { nspAlarmsEntry 1008 }

nspAlarmFirstDate        OBJECT-TYPE
        SYNTAX          OCTET STRING
        MAX-ACCESS      read-only
        STATUS          current
        DESCRIPTION     "Represents the raised date in ASN.1
format
                                         for the NSP forwarded alarm on the managed object"

```

```

 ::= { nspAlarmsEntry 1010 }

nspAlarmClearDate      OBJECT-TYPE
SYNTAX                OCTET STRING
MAX-ACCESS            read-only
STATUS                current
DESCRIPTION           "Represents the clear date in ASN.1 format
for the NSP forwarded alarm on the managed object"
 ::= { nspAlarmsEntry 1011 }

nspAlarmCriticalCount OBJECT-TYPE
SYNTAX                Integer32
MAX-ACCESS            read-only
STATUS                current
DESCRIPTION           "Represents the number of critical events
for the NSP forwarded alarm on the managed object"
 ::= { nspAlarmsEntry 1012 }

nspAlarmMajorCount     OBJECT-TYPE
SYNTAX                Integer32
MAX-ACCESS            read-only
STATUS                current
DESCRIPTION           "Represents the number of major events
for the NSP forwarded alarm on the managed object"
 ::= { nspAlarmsEntry 1013 }

nspAlarmMinorCount     OBJECT-TYPE
SYNTAX                Integer32
MAX-ACCESS            read-only
STATUS                current
DESCRIPTION           "Represents the number of minor events
for the NSP forwarded alarm on the managed object"
 ::= { nspAlarmsEntry 1014 }

nspAlarmWarningCount   OBJECT-TYPE
SYNTAX                Integer32
MAX-ACCESS            read-only
STATUS                current
DESCRIPTION           "Represents the number of warning events
for the NSP forwarded alarm on the managed object"
 ::= { nspAlarmsEntry 1015 }

nspAlarmAcknowledged  OBJECT-TYPE

```

```

        SYNTAX          INTEGER { false ( 0 ) , true ( 1 ) }
        MAX-ACCESS      read-write
        STATUS          current
        DESCRIPTION     "Represents the acknowledged status
                        for the NSP forwarded alarm of the managed object"
        ::= { nspAlarmsEntry 1016 }

        fwdVersion      OBJECT-TYPE
        SYNTAX          OCTET STRING
        MAX-ACCESS      read-only
        STATUS          current
        DESCRIPTION     "Current version of the NSP Forwarding
SNMP sub-agent"
        ::= { forwarding 10 }

        fwdStatus       OBJECT-TYPE
        SYNTAX          INTEGER { allGood ( 0 ) , failure ( 1 )
}
        MAX-ACCESS      read-only
        STATUS          current
        DESCRIPTION     "Global state of the NSP Forwarding SNMP
sub-agent"
        ::= { forwarding 11 }

        ituAlarmEvent   OBJECT IDENTIFIER
        ::= { forwarding 733 }

        otherAlarm      NOTIFICATION-TYPE
        OBJECTS         { nspAlarmId, nspManagedObjectId,
nspAlarmLastEventTime, nspAlarmProbableCause, nspAlarmPerceivedSeverity,
nspAlarmTrendIndication, nspAlarmThresholdLevel, nspAlarmObservedValue,
nspAlarmAdditionalText, nspAlarmSpecificProblem, nspAlarmFirstDate,
nspAlarmClearDate, nspAlarmCriticalCount, nspAlarmMajorCount, nspAlarmMinorCount,
nspAlarmWarningCount, nspAlarmAcknowledged, nspManagedObjectName,
nspManagedObjectDN }

        STATUS          current
        DESCRIPTION     "Represents the event type for other
alarms as per [X.721],[X.733] and [X.736]"
        ::= { ituAlarmEvent 1 }

        communicationAlarm NOTIFICATION-TYPE
        OBJECTS         { nspAlarmId, nspManagedObjectId,
nspAlarmLastEventTime, nspAlarmProbableCause, nspAlarmPerceivedSeverity,
nspAlarmTrendIndication, nspAlarmThresholdLevel, nspAlarmObservedValue,
nspAlarmAdditionalText, nspAlarmSpecificProblem, nspAlarmFirstDate,
nspAlarmClearDate, nspAlarmCriticalCount, nspAlarmMajorCount, nspAlarmMinorCount,
nspAlarmWarningCount, nspAlarmAcknowledged, nspManagedObjectName,
nspManagedObjectDN }

        STATUS          current
        DESCRIPTION     "Represents the event type for the
communication alarms as per [X.721],[X.733] and [X.736]"
        ::= { ituAlarmEvent 2 }

        environmentalAlarm NOTIFICATION-TYPE
        OBJECTS         { nspAlarmId, nspManagedObjectId,
nspAlarmLastEventTime, nspAlarmProbableCause, nspAlarmPerceivedSeverity,
nspAlarmTrendIndication, nspAlarmThresholdLevel, nspAlarmObservedValue,
nspAlarmAdditionalText, nspAlarmSpecificProblem, nspAlarmFirstDate,
nspAlarmClearDate, nspAlarmCriticalCount, nspAlarmMajorCount, nspAlarmMinorCount,
nspAlarmWarningCount, nspAlarmAcknowledged, nspManagedObjectName,
nspManagedObjectDN }

```

```

nspManagedObjectDN }

      STATUS          current
      DESCRIPTION      "Represents the event type for the
environment alarms as per [X.721],[X.733] and [X.736]"

      ::= { ituAlarmEvent 3 }

equipmentAlarm  NOTIFICATION-TYPE
      OBJECTS          { nspAlarmId, nspManagedObjectId,
nspAlarmLastEventTime, nspAlarmProbableCause, nspAlarmPerceivedSeverity,
nspAlarmTrendIndication, nspAlarmThresholdLevel, nspAlarmObservedValue,
nspAlarmAdditionalText, nspAlarmSpecificProblem, nspAlarmFirstDate,
nspAlarmCriticalCount, nspAlarmMajorCount, nspAlarmMinorCount,
nspAlarmWarningCount, nspAlarmAcknowledged, nspManagedObjectName,
nspManagedObjectDN }

      STATUS          current
      DESCRIPTION      "Represents the event type for the
equipment alarms as per [X.721],[X.733] and [X.736]"

      ::= { ituAlarmEvent 4 }

integrityViolation  NOTIFICATION-TYPE
      OBJECTS          { nspAlarmId, nspManagedObjectId,
nspAlarmLastEventTime, nspAlarmProbableCause, nspAlarmPerceivedSeverity,
nspAlarmTrendIndication, nspAlarmThresholdLevel, nspAlarmObservedValue,
nspAlarmAdditionalText, nspAlarmSpecificProblem, nspAlarmFirstDate,
nspAlarmCriticalCount, nspAlarmMajorCount, nspAlarmMinorCount,
nspAlarmWarningCount, nspAlarmAcknowledged, nspManagedObjectName,
nspManagedObjectDN }

      STATUS          current
      DESCRIPTION      "Represents the event type for the
integrity violation as per [X.721],[X.733] and [X.736]"

      ::= { ituAlarmEvent 5 }

processingErrorAlarm  NOTIFICATION-TYPE
      OBJECTS          { nspAlarmId, nspManagedObjectId,
nspAlarmLastEventTime, nspAlarmProbableCause, nspAlarmPerceivedSeverity,
nspAlarmTrendIndication, nspAlarmThresholdLevel, nspAlarmObservedValue,
nspAlarmAdditionalText, nspAlarmSpecificProblem, nspAlarmFirstDate,
nspAlarmCriticalCount, nspAlarmMajorCount, nspAlarmMinorCount,
nspAlarmWarningCount, nspAlarmAcknowledged, nspManagedObjectName,
nspManagedObjectDN }

      STATUS          current
      DESCRIPTION      "Represents the event type for the
processing error alarms as per [X.721],[X.733] and [X.736]"

      ::= { ituAlarmEvent 10 }

qualityOfServiceAlarm  NOTIFICATION-TYPE
      OBJECTS          { nspAlarmId, nspManagedObjectId,
nspAlarmLastEventTime, nspAlarmProbableCause, nspAlarmPerceivedSeverity,
nspAlarmTrendIndication, nspAlarmThresholdLevel, nspAlarmObservedValue,
nspAlarmAdditionalText, nspAlarmSpecificProblem, nspAlarmFirstDate,
nspAlarmCriticalCount, nspAlarmMajorCount, nspAlarmMinorCount,
nspAlarmWarningCount, nspAlarmAcknowledged, nspManagedObjectName,
nspManagedObjectDN }

      STATUS          current
      DESCRIPTION      "Represents the event type for the quality

```

```

of service alarms as per [X.721],[X.733] and [X.736]"

 ::= { ituAlarmEvent 11 }

ituAlarmEventGroup      NOTIFICATION-GROUP
NOTIFICATIONS { communicationAlarm, environmentalAlarm,
equipmentAlarm, integrityViolation, otherAlarm, processingErrorAlarm,
qualityOfServiceAlarm }

STATUS                  current
DESCRIPTION "ITU alarm Event notifications"
 ::= { forwarding 500 }

managedObject OBJECT-GROUP
OBJECTS { nspManagedObjectClassDescription,
nspManagedObjectClassId, nspManagedObjectClassIdRef, nspManagedObjectClassName,
nspManagedObjectClassRowStatus, nspManagedObjectId, nspManagedObjectIdRef,
nspManagedObjectName, nspManagedObjectParent, nspManagedObjectRowStatus,
nspManagedObjectDN }

STATUS                  current
DESCRIPTION "Data related to NSP managed objects"
 ::= { forwarding 200 }

alarm     OBJECT-GROUP
OBJECTS { nspAlarmAcknowledged,
nspAlarmAdditionalText, nspAlarmClearDate, nspAlarmCriticalCount,
nspAlarmFirstDate, nspAlarmId, nspAlarmLastEventTime, nspAlarmMajorCount,
nspAlarmMinorCount, nspAlarmObservedValue, nspAlarmPerceivedSeverity,
nspAlarmProbableCause, nspAlarmEventType, nspAlarmRowStatus,
nspAlarmSpecificProblem, nspAlarmThresholdLevel, nspAlarmTrendIndication,
nspAlarmWarningCount }

STATUS                  current
DESCRIPTION "Data related to NSP alarms"
 ::= { forwarding 300 }

forward OBJECT-GROUP
OBJECTS { fwdVersion, fwdStatus}
STATUS      current
DESCRIPTION "Data related to NSP forwarding module"
 ::= { forwarding 100 }

END

```