

JD Edwards World

Electronic Burst and Bind Guide

Release A9.4

E58807-02

June 2015

Describes how to use the Electronic Burst and Bind (EBB) to eliminate much of the cost and effort generally required to generate, collate and distribute reports and documents.

JD Edwards World Electronic Burst and Bind Guide, Release A9.4

E58807-02

Copyright © 2015, Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

Contents

Preface	ix
Audience	ix
Documentation Accessibility	ix
Related Information	ix
Conventions	ix
1 Overview to Electronic Burst and Bind	
1.1 Basic Processes of EBB.....	1-1
1.1.1 Bursting	1-2
1.1.2 Binding	1-3
1.1.3 Routing	1-4
1.2 Process Flow	1-4
1.3 About This Guide.....	1-5
1.3.1 Before You Begin.....	1-5
Part I EBB Setup and Environment	
2 Overview to EBB Setup and Environment	
2.1 About EBB Setup and Environment.....	2-1
2.1.1 Before You Begin.....	2-1
2.1.2 What You Should Know About.....	2-2
3 Update EBB Setup Files	
3.1 Updating EBB Setup Files.....	3-1
3.1.1 Before You Begin.....	3-1
4 Customize the EBB Processing Environment	
4.1 Customizing the EBB Processing Environment	4-1
Part II Versions	
5 Overview to Versions	
5.1 About EBB Versions	5-1

6	Add an EBB Version	
6.1	Adding an EBB Version	6-1
6.1.1	Before You Begin.....	6-1
7	Maintain EBB Versions	
7.1	Maintaining EBB Versions.....	7-1
7.1.1	Options	7-1
7.2	Copying a Version	7-1
7.3	Deleting a Version.....	7-2
7.4	Changing the Defaults.....	7-3
8	Use a Model Version	
8.1	Using a Model Version.....	8-1
8.1.1	Setting up a Model Version.....	8-1
8.1.2	Creating a New Version Using a Model.....	8-1
Part III Reports Selection		
9	Overview to Reports Selection	
9.1	About EBB Reports Selection	9-1
10	Access EBB Reports Selection	
10.1	Accessing EBB Reports Selection.....	10-1
10.1.1	Options	10-2
10.1.2	Function Exits.....	10-2
11	Add a Report to a Version	
11.1	Adding a Report to a Version	11-1
11.1.1	What You Should Know About.....	11-2
12	Sequence Reports	
12.1	Sequencing Reports	12-1
Part IV Burst and Bind Criteria		
13	Overview to Burst and Bind Criteria	
13.1	About Burst and Bind Criteria	13-1
13.1.1	What is Burst Criteria?	13-1
13.1.2	What is Bind Criteria?	13-1
14	Set Up Burst Areas Using Data Description Specification (DDS)	
14.1	DDS Considerations	14-1
14.2	Setting Up Burst Areas Using DDS.....	14-1

14.2.1	Before You Begin.....	14-2
15	Set Up Burst Areas Using Spool Files	
15.1	Setting Up Burst Areas Using Spool Files	15-1
15.2	Setting Up FASTR and World Writer Reports for Burst Criteria.....	15-4
16	Work with Burst Areas	
16.1	Working with Burst Areas.....	16-1
16.1.1	Function Exits.....	16-3
17	Print a Version Information Report	
17.1	Printing a Version Information Report.....	17-1
Part V Select Keys		
18	Overview to Select Keys	
18.1	About Select Keys	18-1
19	Load Select Keys	
19.1	Loading Select Keys.....	19-1
19.1.1	What You Should Know About.....	19-1
19.2	Loading Select Keys for a Single Spool File	19-1
19.3	Loading Select Keys for Multiple Spool Files	19-2
20	Add Select Keys	
20.1	Add Select Keys.....	20-1
20.1.1	Options	20-3
Part VI Routing Functions		
21	Overview to Routing Functions	
21.1	About Routing Functions.....	21-1
21.2	What is a Routing Function?	21-1
21.2.1	Demo Routing Functions.....	21-1
21.2.2	The PRINT Routing Function	21-2
21.3	Command Line Entry Requirements	21-2
21.4	Keywords	21-2
22	Create a Routing Function	
22.1	Creating a Routing Function	22-1
22.1.1	What You Should Know About.....	22-1
22.2	Creating a Routing Function from an Existing Function	22-1
22.3	Creating a New Routing Function.....	22-3

23	Delete a Routing Function	
23.1	Deleting a Routing Function in EBB.....	23-1
23.2	Deleting a Routing Function from Select Keys.....	23-2
24	Assign Routing Functions to Select Keys	
24.1	Assigning Routing Functions to Select Keys	24-1
24.1.1	Before You Begin.....	24-1
24.2	Assigning the PRINT Routing Function.....	24-1
24.3	Assigning a Routing Function to a Single Select Key	24-4
24.3.1	Before You Begin.....	24-4
24.4	Assigning a Routing Function to Multiple Select Keys.....	24-8
24.4.1	To assign a routing function to multiple select keys	24-8
25	Change Select Key Parameters	
25.1	Changing Parameters for a Select Key	25-1
26	Print the Entity/Functions Report	
26.1	Printing the Entity/Functions Report.....	26-1
Part VII Substitute Select Keys		
27	Overview to Substitute Select Keys	
27.1	About Substitute Select Keys.....	27-1
27.1.1	Examples Using Substitute Select Keys.....	27-1
28	Define Substitute Select Keys	
28.1	Defining Substitute Select Keys	28-1
29	Generate the Cross-Reference Index	
29.1	Generating the Cross-Reference Index	29-1
30	Update the Cross-Reference Table	
30.1	Before You Begin.....	30-1
30.2	Adding a DREAM Writer Report Version for P98E08	30-1
30.3	Identifying the Version	30-3
30.4	Defining Version Parameters	30-4
30.5	Specifying Processing Option Revisions	30-5
30.5.1	Processing Options	30-5
30.6	Selecting Data	30-5
30.7	Assigning Sequence Numbers to Select Keys.....	30-6
30.7.1	Function Exits.....	30-7

Part VIII Monitor

31	Overview to Monitor	
31.1	About the Monitor	31-1
31.1.1	Before You Begin.....	31-1
32	Move Spool Files to EBBSTART	
32.1	Moving Spool Files to EBBSTART.....	32-1
33	Start the Monitor	
33.1	Starting the Monitor	33-1
33.1.1	Before You Begin.....	33-1
33.1.2	What You Should Know About.....	33-1
34	End the Monitor	
34.1	Ending the Monitor	34-1
34.1.1	What You Should Know About.....	34-2
35	Display the EBB Message Queue	
35.1	Displaying the EBB Message Queue	35-1
35.1.1	Function Keys.....	35-2
36	Clear the EBB History Log	
36.1	Clearing the EBB History Log	36-1
37	View the EBB Process Report	
37.1	Viewing the EBB Process Report	37-1
38	Electronic Burst and Bind Processing Option	
38.1	EBB-Substitute Keys Demo (P98E08).....	38-1
A	Tips and Techniques	
A.1	Display the JD Edwards World Release Level	A-1
A.2	Override Same Spool File Names with % Menu	A-1
A.3	Correct Inconsistent Page Breaks on FASTR Reports.....	A-1
A.4	Print and Hold a Spool File	A-2
A.5	Change the Form Type.....	A-2
A.6	Change User Data Attributes	A-2
A.7	Perform Duplex Printing	A-2
A.8	Send Spool Files Across Network.....	A-2
A.9	Troubleshooting Tips	A-2

B Routing Functions

C EBB Messages

D EBB Examples

D.1	Producing a Basic Report Version	D-1
D.2	Producing an Advanced Report Version.....	D-12
D.2.1	What You Should Know About.....	D-18

Index

Preface

Welcome to the JD Edwards World Electronic Burst and Bind Guide.

Audience

This guide is intended for implementers and end users of JD Edwards World Electronic Burst and Bind.

Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc>.

Access to Oracle Support

Oracle customers that have purchased support have access to electronic support through My Oracle Support. For information, visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info> or visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs> if you are hearing impaired.

Related Information

For additional information about JD Edwards World applications, features, content, and training, visit the JD Edwards World pages on the JD Edwards Resource Library located at:

<http://learnjde.com>

Conventions

The following text conventions are used in this document:

Convention	Meaning
boldface	Indicates cautionary information or terms defined in the glossary.
<i>italic</i>	Indicates book titles or emphasis.

Overview to Electronic Burst and Bind

Electronic Burst and Bind (EBB) eliminates much of the cost and effort generally required to generate, collate and distribute reports and documents. EBB works seamlessly with JD Edwards World software, FASTR and World Writer reports.

This chapter contains these topics:

- [Section 1.1, "Basic Processes of EBB,"](#)
- [Section 1.2, "Process Flow,"](#)
- [Section 1.3, "About This Guide."](#)


1.1 Basic Processes of EBB

Electronic Burst and Bind uses the following processes:

- Bursting
- Binding
- Routing


Consider the following example. You run an Income Statement and a Balance Sheet for three companies. The system creates two spools. One includes the income statements and the other includes the balance sheets.

Figure 1-1 Beginning Spool File 1



1.1.1 Bursting


Using the criteria you specify, EBB separates a single spool report into multiple spool files. This prevents you from having to run and then separate Dream Writer reports. The burst criterion in this example is the Company Number.

Figure 1-2 Illustration of Multiple Spool Files

1.1.2 Binding

After the system separates a spool file, the binding process selects specific pages and collates them into the print order you designate. Then, the system creates separate spool files that contain the sorted reports.

In the following example, the Balance Sheet and Income Statement for each Company are bound together.


Figure 1-3 Spool Files A, B, and C

1.1.3 Routing

The routing process distributes each output spool file to one or more destinations. You can also assign functions, such as printing, to the output spool file, depending on your requirements.

In the following example, the spool file contains the Balance Sheet and Income Statement for Company 003 which the system routes to multiple destinations.


Figure 1-4 Spool File C



1.2 Process Flow

Depending on your needs, you can use the basic Electronic Burst and Bind processes of bursting, binding, and routing reports individually or together. The following illustrates the process flow of the EBB.

Figure 1-5 Process Flow of the EBB



1.3 About This Guide

The Electronic Burst and Bind guide includes various topics in the EBB process. It contains the following information:

- EBB setup and environment
- Monitor
- Versions
- Reports selection
- Burst and bind criteria
- Select keys
- Routing functions
- Substitute select keys

1.3.1 Before You Begin

- To use EBB, you must have a working knowledge of JD Edwards World software and System i operations.

Part I

EBB Setup and Environment

This part contains these chapters:

- [Chapter 2, "Overview to EBB Setup and Environment,"](#)
- [Chapter 3, "Update EBB Setup Files,"](#)
- [Chapter 4, "Customize the EBB Processing Environment."](#)

Overview to EBB Setup and Environment

This chapter contains the topic:

- [Section 2.1, "About EBB Setup and Environment."](#)

2.1 About EBB Setup and Environment

This section contains important information about maintaining your EBB processing queues and EBB data files. Whether you are a new user or proficient with EBB, you should read and understand this section.

EBB requires a job queue and two output queues, referred to as processing queues. Before you can use EBB, identify the appropriate processing queues for your EBB setup. If one or more queues do not exist, you must create them. While you can name your processing queues whatever you like, JD Edwards World recommends the following three queues:

- EBBJOBQ
- EBBERRQ
- EBBFINAL

After you create the processing queues, you must run the EBB Setup File Maintenance program (P98E99) to update your EBB data files. When you run P98E99, you must indicate the appropriate processing queues.

Note: You must create a processing queue named EBBSTART for storing reports.

This section includes of the following:

- Update the EBB setup files
- Customize the EBB processing environment

2.1.1 Before You Begin

Ensure these prerequisites are met:

- Ensure you are proficient with JD Edwards World software and an System i operator.
- Ensure that your JD Edwards World release is A9.1 or higher. To verify the release, choose Product Information from the Help menu.

- Ensure there is a minimum of 2 megabytes for file storage and 5 megabytes programs.

2.1.2 What You Should Know About

Topic	Description
Action Code Security and EBB	<p>The Action Code Security program P00031 uses the Software Versions Repository (SVR) Master file F9801. The EBB objects are not in the SVR. If you do not add an SVR record for the EBB programs, the JD Edwards World programs do not recognize the EBB programs. Depending upon your Action Code Security set up, the system might lock you out of EBB.</p> <p>If you install EBB and want to use Action Code Security, you must add an SVR record for each of the following:</p> <ul style="list-style-type: none"> EBB - Processing Program P6002 EBB - Substitute Select Key Batch Update P6008 EBB - Bind Version ID Maintenance P6010 EBB - Work with Function Descriptions P6025 EBB - Clear History File P6030 EBB - Version Information Report P6050 EBB - Entity/Function Report P6052 EBB - Setup Parameters Maintenance P6099 <p>It is not necessary for you to have the source for these programs, but you must give each of them a record in the F9801 file by completing the top portion of the SVR screen.</p> <p>On Software Versions Repository, for each program, enter the program name in the Description field, for example EBB - Processing Program. Enter the program number in the Member ID and Base Member Name fields. The balance of the fields contain the following data for each program:</p> <ul style="list-style-type: none"> ■ Function Code: RPG ■ Function Use: 130 ■ System Code and Reporting System: 991

Update EBB Setup Files

This chapter contains the topic:

- [Section 3.1, "Updating EBB Setup Files."](#)

3.1 Updating EBB Setup Files

To update your EBB setup files, EBB must already exist on your system and use system code 98. If EBB exists on your system for releases prior to A9.1, you must convert from your previous version.

3.1.1 Before You Begin

Identify the job queue, message out queue, and final out queue. Ensure that the output queue for storing reports, EBBSTART, exists. If any of these processing queues do not exist, you must create them.


To update EBB setup files

Navigation

From Electronic Burst and Bind (G98E), choose EBB Setup File Maintenance


1. On EBB Setup File Maintenance, complete the following fields:
 - `Current EBB data library

Figure 3–1 EBB File Setup Maintenance screen



2. To validate the fields, click Enter.
3. To proceed with the update, choose Update (F10).

Figure 3–2 EBB Setup File Maintenance (Update) screen



4. On EBB Setup File Maintenance, complete the following fields:
 - `Jobq to Run EBB Monitor In
 - `OUTQ to Receive Error Output
 - `Want a banner page to print?

- `JD Edwards World DREAM Writer Source File
- `Write audit log records?

Field	Explanation
Convert from previous EBB version	Indicates whether you want to convert EBB data files from a previous version of EBB. The valid values are: Y - convert data files N - do not convert data files If you enter Y, you must also enter the name of your current production data library. If you enter N, EBB proceeds to the EBB Setup File Maintenance screen without updating any files.
Previous EBB data library	The previous production data library.
Current EBB data library	The current production data library.
Monitor Delay Time	The number of seconds between successive runs of the EBB monitor. JD Edwards World recommends 300 to 900 seconds (5 to 15 minutes). This does not result in undue processing requirements on the system, yet is sufficient for the EBB monitor to burst reports.
JOBQ to run EBB monitor in	The default job queue. JD Edwards World recommends the default, EBBJOBQ, unless you changed the name during installation.
OUTQ to receive bound output	The default out queue to which burst and/or bound reports are stored. JD Edwards World recommends the default, EBBFINAL, if you want to store the burst and/or bound reports to a separate out queue.
OUTQ to receive error output	The default output queue to which messages are written when select keys are not found. JD Edwards World recommends the default, EBBERRQ.
Function	PRINT is the default routing function and must always be the first function for a select key. You cannot modify this field. Note: For an individual select key, you can use the PRINT routing function to override the receiving output queue.
Want a banner page to print	Indicates whether a banner page prints with the report. The valid options are: Y - prints a banner page N - does not print a banner page The default is Y. You can override this option for a version ID using individual select keys.
Keep spool files	Indicates whether the monitor stores or deletes the original unburst reports. Valid values are: Y - store the original reports N - delete the original reports JD Edwards World recommends that you set this to Y initially.
JD Edwards World DREAM Writer Source File	The Source File Name field contains the name of the file where the source for an object exists. In the program generator File Specifications this name is defaulted to "JDESRC". In combination with the source library name it identifies where the program generator can find the source for each data file, display file or report file which it must analyze to create the data field parameters. As used in the automated installation processing file this is the source file of an object at the time the object was created.

Field	Explanation
Source library	The name of the source library.
Write audit log records	Indicates whether EBB tracks and saves the processing results of an EBB version. The valid values are: Y - saves an audit log N - does not save an audit log

Customize the EBB Processing Environment

This chapter contains the topic:

- [Section 4.1, "Customizing the EBB Processing Environment."](#)

4.1 Customizing the EBB Processing Environment

The install process creates an EBBJOB in object library. EBBJOB uses the EBB Submit the monitor program. You might want to customize this job description for your environment. For example, if you are using a special user profile, customize the job description by including the special user profile on EBBJOB.

To run EBB using a special user profile, the profile must be active with the appropriate JD Edwards World authorizations.

To customize the EBB processing environment

1. End the subsystem where you run EBB.
2. Locate the next available sequence number on your system by entering DSPSBSD SBSD(XXXXXX) on the command line.

Replace XXXXXX with the name of the subsystem.
3. Choose Job Queue Entries.

Sequence numbers appear to the left of each jobq entry.
4. To add the EBB jobq to the subsystem, enter the following on the command line:

`ADDJOBQE SBSD(*LIBL/XXXXXX) JOBQ(EBBLIB/EBBJOBQ) SEQNBR(##)`

Replace XXXXXX with the name of the subsystem and ## with the next available sequence number for the subsystem.
5. Restart the subsystem where EBB runs.

Part II

Versions

This part contains these chapters:

- [Chapter 5, "Overview to Versions,"](#)
- [Chapter 6, "Add an EBB Version,"](#)
- [Chapter 7, "Maintain EBB Versions,"](#)
- [Chapter 8, "Use a Model Version."](#)

Overview to Versions

This chapter contains the topic:

- [Section 5.1, "About EBB Versions."](#)

5.1 About EBB Versions

An EBB Version is a collection of instructions that burst, bind, and route one or more reports. There is no limit on the number of EBB versions you can set up.

Each EBB Version identifies one or more reports to be burst and bound. The binding process occurs whenever you specify two or more reports for a particular EBB Version. Unless the version references a model version, each EBB Version contains a set of select keys. The select keys might use only the default routing or include other routing functions.

This section includes the following:

- Add a version
- Maintain a version
- Use a model version

Add an EBB Version

This chapter contains the topic:

- [Section 6.1, "Adding an EBB Version."](#)

6.1 Adding an EBB Version

The first step in using Electronic Burst and Bind is to add an EBB version. You must enter values in all fields on the Add EBB Version ID screen or accept the defaults. After a version exists, you can define the burst area and routing instructions.

6.1.1 Before You Begin

- Move the spool files with which you want to work to EBBSTART.
- Clear the EBB Monitor. On the Electronic Burst and Bind menu (G98E), choose End EBB Monitor. See [Chapter 34, "End the Monitor"](#) for information about moving spool files and using the EBB Monitor.


To add a version

Navigation

From Electronic Burst and Bind (G98E), choose Maintain EBB Versions

1. On Maintain EBB Versions, choose EBB Version - Set Up (F6).
2. On Add EBB Version ID, complete the following fields:
 - `Version Description
 - `Error Outq
 - `Want a banner
 - `Version for select keys

Figure 6–1 Add EBB Version ID screen



EBB Reports Selection displays with reports to burst and bind.

Field	Explanation
EBB Version ID	A unique name up to ten characters without blanks.
Version Description	Short, informative text that identifies a version.
Receiving Outq	The processing queue where the burst and/or bound spool files are sent if no other output queue is specified. This output queue will be the default for this version. JD Edwards World recommends you do not enter EBBSTART because the monitor looks for spool files to be burst in this output queue.
Error Outq	Accept the default, EBBERRQ, or enter another one. The error output queue is where spool files are sent if the select key is not found or if the functions are set up incorrectly. You can then choose to move the file from the error output queue to another output queue. Check the EBBERRQ to see what report must be distributed manually each time the monitor runs.
Function	PRINT is the default routing function and must always be the first function for a select key. You cannot modify this field. Note: For an individual select key, you can use the PRINT routing function to override the receiving output queue.
Want a banner	Indicates whether a banner page prints with the report. The valid options are: Y - prints a banner page N - does not print a banner page The default is Y. You can override this option for a version ID using individual select keys.

Field	Explanation
Keep spool file	Indicates whether the monitor stores or deletes the original unburst reports. Valid values are: Y - store the original reports N - delete the original reports JD Edwards World recommends that you set this to Y initially.
Version for select keys	The version ID that is used as the model for a new version. If a model version is not used, leave this field blank. It defaults to the version ID you are setting up.

Maintain EBB Versions

This chapter contains these topics:

- [Section 7.1, "Maintaining EBB Versions,"](#)
- [Section 7.2, "Copying a Version,"](#)
- [Section 7.3, "Deleting a Version,"](#)
- [Section 7.4, "Changing the Defaults."](#)

7.1 Maintaining EBB Versions

After you set up a version, it appears in the versions list on the Maintain EBB Versions screen. You can perform various functions with the version.

7.1.1 Options

You can enter the following values in the Option field on the Maintain EBB Versions screen:

Option	Description
1	Selects a version with which you can work.
2	Displays the Select Keys Maintenance screen for the corresponding EBB version.
3	Display the Maintain EBB Versions screen where you can modify the EBB version.
5	Displays the Spool File Selection screen where you can select and sequence reports in the spool file.
7	Displays the EBB - Copy Version ID where you can duplicate the EBB version.

7.2 Copying a Version

Navigation

From Electronic Burst and Bind (G98E), choose Maintain EBB Versions

Copy an existing version to quickly and easily create a new version based on the original. When you copy a version, you specify another name and modify the output parameters, leaving the original version in tact.


Note: When you change the model version to which a duplicate version refers, the system no longer uses the select keys and routing functions from the original model version. Instead, the monitor uses the select keys and routing functions with the model version. To avoid confusion, delete the select keys from the duplicate version.

If you change a duplicate version so that it doesn't refer to any model, then you must select burst areas, preload select keys, and attach routing functions.

To copy a version

1. On Maintain EBB Versions, enter 7 in the Option field for the version you want to copy.

Figure 7-1 Add EBB Version ID (Copy a Version) screen



2. On Add EBB Version ID, complete the following fields:

- `Version Description
- `Error Outq
- `Want a banner
- `Version for select keys

If the EBB version ID you enter does not exist, an error displays. Enter the correct model version ID.

7.3 Deleting a Version

If you have set up a version in error or it is no longer in use, you can delete the version. Ensure if you delete a model version, no duplicate versions exist that use the model.

To delete a version

On Maintain EBB Versions, enter 9 in the Option field for the version you want to delete.

The Maintain EBB Versions screen refreshes and the version no longer displays.


7.4 Changing the Defaults

You can modify the version output and model version parameters for each version.

To change the defaults

1. On Maintain EBB Versions, enter 3 in the Option field for the version you want to copy.

Figure 7–2 *Version Output Parameters screen*



If you only need to verify the defaults, review the fields and exit (F3) the window.

2. On Version Output Parameters, complete the following fields:
 - `Default Outque
 - `Default Banner
 - `Version for Select keys

Note: Default Banner is overridden at the individual print function level. If you do not want the banner page to print, change Print Banner Page for each routing function to N on the Version Output Parameters screen.

Use a Model Version

This chapter contains the topic:

- [Section 8.1, "Using a Model Version."](#)

8.1 Using a Model Version

A model version is an EBB Version to which other versions refer for select keys and routing functions, but which contain different report criteria. By using a model version, you only need to make changes for select keys and routing functions in one place. Other versions refer to the model by naming the model using the Maintain EBB Version program.

To use a model version, complete the following tasks:

- Setting up a model version
- Creating a new version using a model

8.1.1 Setting up a Model Version

A model version is a working version. You add a model version just as you add any other version. After you select reports, define select keys, and attach routing functions, you can use the model version to create subsequent versions or refer existing versions to the model. You should consider using the name model when creating the model to indicate it is a model version.

8.1.2 Creating a New Version Using a Model

To create a new version using a model

1. On Maintain EBB Version, choose EBB Version - Set Up (F6).
2. Complete the following fields:
 - `Version Description
 - `Error Outq
 - `Want a banner
3. `Enter the model in the following field:
 - "Version for Select keys

Part III

Reports Selection

This part contains these chapters:

- [Chapter 9, "Overview to Reports Selection,"](#)
- [Chapter 10, "Access EBB Reports Selection,"](#)
- [Chapter 11, "Add a Report to a Version,"](#)
- [Chapter 12, "Sequence Reports."](#)

Overview to Reports Selection

This chapter contains the topic:

- [Section 9.1, "About EBB Reports Selection."](#)

9.1 About EBB Reports Selection

Use the EBB Reports Selection program (P98E12) to specify and sequence reports for a version.

You can specify one or more reports that run for a version. You can select any spool file report, including reports you create using:

- DREAM Writer
- World Writer
- FASTR

To work with EBB Reports Selections, perform the following tasks:

- Access the EBB Reports Selections application
- Add a report to a version
- Sequence reports

Access EBB Reports Selection

This chapter contains the topic:

- [Section 10.1, "Accessing EBB Reports Selection."](#)

10.1 Accessing EBB Reports Selection

You can access EBB Reports Selection for any EBB version from the Maintain EBB Version screen.


Navigation

From Electronic Burst and Bind (G98E), choose **Maintain EBB Versions**

To access EBB Reports Selection

On Maintain EBB Versions, enter 1 in the Option field to access the EBB version.

Figure 10–1 EBB Reports Selection screen



10.1.1 Options

You can use the following values in the Option field on the EBB Reports Selection screen:

Option	Description
1	Displays the Burst Selection Setup area on the screen for defining the burst area on a report.
2	Displays the Substitute Key Maintenance window for working with substitute select keys.
9	Deletes the report from the EBB version.

10.1.2 Function Exits

Choose Display Spool file for selection (F8) to display the Spool File Selection screen and add reports to an EBB version.

Add a Report to a Version

This chapter contains the topic:

- [Section 11.1, "Adding a Report to a Version."](#)

11.1 Adding a Report to a Version


After you create a version, you add one or more reports that run in the version. You can add JD Edwards World reports, such as DREAM Writer, World Writer, and FASTR, and other spool file reports.

An EBB version that contains a single report is a burst only version. An EBB version that contains multiple reports must be burst and then bound. You can also use EBB Reports Selection for DREAM Writer reports or the Data Description Specifications (DDS) to set the burst criteria. See [Chapter 14, "Set Up Burst Areas Using Data Description Specification \(DDS\)"](#) for more information about using DDS.

To add a report

1. On EBB Reports Selection, choose Display Spool file for selection (F8).

Figure 11–1 Spool File Selection screen




2. On Spool File Selection, enter the output queue name in which the reports reside, in the OUTQ field.

Note: Place the widest report first in the sequence of reports. EBB truncates data based on the width of the initial report in the version.

3. Perform one of the following:
 - To control the sequence in which the reports process, enter 1 in the Option field and then click Enter each time you select a report.

Figure 11–2 Spool File Selection (Control Sequence) screen



Notice that the term Selected appears at the end of the report line and indicates the report is included in the EBB version.

4. Exit (F3) to the EBB Reports Selection screen.

The reports you select display.

11.1.1 What You Should Know About

Reports	Description
% Menus	% menus produce reports with identical spool file names. Because EBB requires that spool file names be unique, you must use printer overrides on the individual reports to specify a unique spool file name.
Report Limitations	You can include up to 999 reports in an EBB version. The report screen can be up to 100 lines long and 198 characters wide. Each report within a version must have a unique name to ensure that EBB processes the reports correctly.

Reports	Description
Reports you select for burst areas	EBB reports only display the first page when you identify the burst area. Avoid selecting a report that includes a banner page or contains print instructions on the first page.

Sequence Reports

This chapter contains the topic:

- [Section 12.1, "Sequencing Reports."](#)

12.1 Sequencing Reports


If you select more than one report for an EBB version, the system assigns each report a sequence number as you select the reports. This is the order in which the bound reports will appear in the output file. You can change the order in which the system processes reports within a version. You must change the sequence on the EBB Reports Selection screen.

You cannot use sequence numbers that are already in use. For example, you have two reports with sequence numbers 001 and 002 and you want to switch the sequence. You must change the report with sequence number 001 to 003.

To sequence reports

1. On EBB Reports Selection, enter the new number in the Change Sequence field.

Figure 12–1 EBB Report Selection (Sequence Reports) screen



2. Click Enter to exit the Maintain EBB Versions screen.

Note: If you have reports which have different formats, such as landscape and portrait, or reports of different widths or lengths, place the largest report first in the sequence. When EBB creates the Bind spool file, the attributes of the first report determine the attributes for all other reports in the bind.

Part IV

Burst and Bind Criteria

This part contains these chapters:

- [Chapter 13, "Overview to Burst and Bind Criteria,"](#)
- [Chapter 14, "Set Up Burst Areas Using Data Description Specification \(DDS\),"](#)
- [Chapter 15, "Set Up Burst Areas Using Spool Files,"](#)
- [Chapter 16, "Work with Burst Areas,"](#)
- [Chapter 17, "Print a Version Information Report."](#)

Overview to Burst and Bind Criteria

This chapter contains the topic:

- [Section 13.1, "About Burst and Bind Criteria."](#)

13.1 About Burst and Bind Criteria

An advantage of EBB is that you can extract only portions of one or more reports to merge into an output spool file for distribution. You accomplish this using burst criterion. After you create a version that includes one or more reports, you must set up the burst and bind criteria.

To work with Burst and Bind criteria, complete the following tasks:

- Set up burst areas using Data Description Specifications (DDS)
- Set up burst areas using spool files
- Work with burst areas
- Print a version information report

13.1.1 What is Burst Criteria?

You choose burst criteria for an area or portion of data in a spool report. When you define burst criteria, you identify the columns and rows within the report. You are not selecting data.

When EBB processes a report, the report bursts when data in the burst area does not match the burst area on the previous page of the report. For example, suppose the header text, 001 - A Model Accounting Company appears in a specific area on a report. In the same area on another page, the text in that same area reads, 007 - A Model Payroll Company. If you designate the burst area, 001 - A Model Account Company, EBB performs the burst function when the header text changes to 007 - A Model Payroll Company.

You can use EBB for routing only by selecting burst criteria that is the same on every page, such as the header. If the burst area never changes, EBB will not burst the report. The output is the same as the input. You can add multiple routing functions to the version to distribute the reports. See [Chapter 21, "Overview to Routing Functions"](#) for more information about routing.

13.1.2 What is Bind Criteria?

When you select multiple reports for an EBB version, and the data in the burst area exactly matches the data in two or more reports, the reports are burst and then merged

into one spool file. If you select more than one area on a report and want to bind it with another report, binding occurs only if the data in all the areas you select match exactly.

Set Up Burst Areas Using Data Description Specification (DDS)

This chapter contains these topics:

- [Section 14.1, "DDS Considerations,"](#)
- [Section 14.2, "Setting Up Burst Areas Using DDS."](#)

14.1 DDS Considerations

A DDS print file contains the size and position of each line and field within a line. On the AS/400, you can define all database, video, and report communication files through DDS. JD Edwards World software uses DDS for all reports.

The DDS print file is especially useful for bursting large reports. Before you use the DDS print file, you might need to temporarily change the values in the data selection for that specific EBB version. This creates a smaller spool file. After you run the modified DREAM Writer version, be sure to change the data selection to the original values before running the report again.

Some reports, including DREAM Writers, might have optional header areas. When a report has an optional header, the burst criteria on the DDS print file can move relative to the spool file from the same report. If this occurs when EBB runs, you must set up the burst area using spool files, rather than use a DDS print file.

The DDS print file source code might not be available due to the following limitations:

- Installations exclude DDS source from the system due to disk space requirements of the source code.
- Reports that do not support a DDS print file.

When a DDS print file is unavailable, use a spool file to set up the burst area.

See Also:

- [Chapter 15, "Set Up Burst Areas Using Spool Files."](#)

14.2 Setting Up Burst Areas Using DDS

The following procedure uses the DDS print file. You can set up most DREAM Writer reports with a DDS print file.

A select key is the data found in the burst area. See [Chapter 18, "Overview to Select Keys"](#) for more information about select keys.

14.2.1 Before You Begin

- Read this section thoroughly before you use a DDS print file.


To set up burst areas using DDS

Navigation

From **Electronic Burst and Bind (G98E)**, choose **Maintain EBB Versions**


- On **Maintain EBB Versions**, enter 1 in the **Option** field to access the EBB version.
- On **EBB Reports Selection** enter 1 in the option field of the reports for which you want to set up a burst area.

Figure 14–1 EBB Reports Selection (Burst Areas) screen



- In the **Burst Selection Setup** area of **EBB Reports Selection**, enter 1 for **DDS Print File**.

Figure 14–2 EBB Reports Selection (Print) screen



A JD Edwards World Dream Writer Burst Criteria screen displays for confirmation.

Figure 14–3 JDE Dream Writer Burst Criteria screen



4. Change or accept the default values in the following fields:
 - `JD Edwards World Source File
 - `The first page of the report displays.
5. Choose Begin Mark (F8) one character before the area you want to specify as the beginning of the burst (select key) area.

6. Move the cursor one character after the area you want to specify as the end of the burst area.
7. Choose End Mark (F9).

The system highlights only the burst area.

You can mark each row with burst areas individually.

The total of all selections must not exceed 90 characters.

The total key length appears in the top left, just above the ruler.

Note: Control characters that mark the beginning and end of burst areas conceal data characters. For example, if you place the cursor on a data character and mark it as the beginning of the burst area, the character no longer displays. This is normal and does not affect the data when you print the report.

Set Up Burst Areas Using Spool Files

You must designate the area of the report you want to burst. When you burst a FASTR or World Writer report, you must complete additional steps.

This chapter contains these topics:

- [Section 15.1, "Setting Up Burst Areas Using Spool Files,"](#)
- [Section 15.2, "Setting Up FASTR and World Writer Reports for Burst Criteria."](#)

15.1 Setting Up Burst Areas Using Spool Files

Use the following procedure for JD Edwards World spool file reports, such as FASTR and World Writer, and other spool files. You can set up DREAM Writer reports, particularly when the source is unavailable, using this procedure.

See Also:

- [Chapter 16, "Work with Burst Areas"](#) for information on verifying, changing, and unmarking burst areas.


To set up the burst areas using spool files

Navigation

From Electronic Burst and Bind (G98E), choose Maintain EBB Versions


1. On Maintain EBB Versions, enter 1 in the Option field to access the EBB version.
2. On EBB Reports Selection, enter 1 in the Option field of the reports for which you want to set up a burst area.

Figure 15–1 EBB Reports Selection (Spool Files) screen




3. In the Burst Selection Setup area of EBB Reports Selection, enter 2 for Spool File Example.

Figure 15–2 EBB Reports Selection (Spool File Example) screen




4. On Spool File Selection, enter the output queue name in which the spool file resides in the OUTQ field.
 If the spool file is not in that output queue, a message displays. Enter the correct output queue name.
5. Enter 1 in the Option field next to the spool file.

Figure 15–3 Spool File Selection (Output) screen



The Select Key Maintenance screen displays the first page of the spool file.

Figure 15–4 Electronic Burst & Bind screen



6. Move the cursor to the space in front of the data area which you want to specify as the beginning of the burst area and choose Begin Mark (F8).

The system highlights all data that follows.

7. Move the cursor to the space after the data area you want to specify as the end of the burst area and choose End Mark (F9).


The system highlights only the data area for bursting.

Note: You must mark each row with data areas individually. The total of all data areas must not exceed 90 characters. EBB performs the routing functions automatically. See [Chapter 21, "Overview to Routing Functions"](#) for more information about routing functions.

The burst area must be no lower than 50 lines within the report. You must mark the burst area in the same place on every page. In other words, the data area on which you are bursting cannot float or move to another area or different lines of the report.

A value in the Total Key Length field displays on the screen.

Figure 15–5 Electronic Burst & Bind (Total Key Length) screen



15.2 Setting Up FASTR and World Writer Reports for Burst Criteria

After you complete all of the steps for Setting Up Burst Areas Using Spool Files you set up the burst criteria for FASTR or World Writer reports. Access the FASTR or World Writer reports for which you are setting up burst criteria.

To set up FASTR and World Writer reports for burst criteria

1. Select a version.
2. Enter 6 in the Option field for Printer File Overrides.
3. On Printer File Overrides, enter EBBSTART in the Print Queue field.
4. Ensure that the Hold in Print Queue field is set to N.
5. On Additional Parameters, change the Print Cover Page and Print Instructions fields to N.

Work with Burst Areas

This chapter contains the topic:

- [Section 16.1, "Working with Burst Areas."](#)

16.1 Working with Burst Areas

After you set up burst areas, you can perform any of the following tasks:

- To change the burst area
- To unmark all burst areas
- To unmark a single burst area

To change the burst area

Navigation

From Electronic Burst and Bind (G98E), choose Maintain EBB Versions

You use the EBB Reports Selection window to change the row position, column position, and field length. You can also change an existing burst area or add one using this window.


1. On Maintain EBB Versions, enter 1 in the Option field to access the EBB version.
2. On EBB Reports Selection, enter 1 in the Option field of the reports for which you want to change a burst area.
3. In the Burst Selection Setup area on EBB Reports Selection, enter 2 for Spool File Example.
4. On Spool File Selection, enter the output queue name in which the spool file resides in the OUTQ field.

If the spool file is not in that output queue, a message displays. Enter the correct output queue name.

5. Enter 1 in the Option field next to the spool file.


The first page of the report displays on Select Key Maintenance.

Figure 16–1 Electronic Burst & Bind (Change Burst Area) screen



6. Choose Change/ Add (F10).

Figure 16–2 EBB-Row and Column Maintenance screen



The indicators, UPDATE or ADD, display at the top of the EBB - Row and Column Maintenance window. If there are numerous burst areas, page through the window until ADD displays after the last burst area. If there are no burst areas, ADD displays at the top of the window.

7. Page down to locate the burst area you want to modify or to a blank area to add a burst area.
8. On the EBB - Row and Column Maintenance window, complete the following fields:
 - Row
 - Column
 - Length
9. Exit (F3) until you return to the Electronic Burst and Bind menu.

To unmark all burst areas

1. On EBB Select Key Maintenance, choose Unmark All (F22).
The system removes the burst areas highlights on EBB Select Key Maintenance.
2. Set up new burst criteria or Exit (F3) to return to Spool File Selection.

To unmark a single burst area

1. On EBB Select Key Maintenance, choose Change/ Add (F10).
The EBB - Row and Column Maintenance window displays.
2. Page down to locate the burst area you want to unmark, clear the following fields and click Enter.
 - `Column
 - `EBB Select Key Maintenance reflects the change to the burst areas.
3. Exit (F3) to return to Spool File Selection.

16.1.1 Function Exits

Use these functions on Select Key Maintenance to perform the following tasks:

- Move Left (F19) to view the left side of display
- Move Right (F20) to view the right side of display

Print a Version Information Report

This chapter contains the topic:

- [Section 17.1, "Printing a Version Information Report."](#)

17.1 Printing a Version Information Report

Print a version information report to view the defaults and burst criteria for each spool file. The details and parameters you define for each EBB version display.

To print a version information report

Navigation

From Electronic Burst and Bind (G98E), choose Version Information Report

The following message displays on the menu: *Version Information Report submitted to batch*

Part V

Select Keys

This part contains these chapters:

- [Chapter 18, "Overview to Select Keys,"](#)
- [Chapter 19, "Load Select Keys,"](#)
- [Chapter 20, "Add Select Keys,"](#)
- [Chapter 38, "Electronic Burst and Bind Processing Option."](#)

Overview to Select Keys

This chapter contains the topic:

- [Section 18.1, "About Select Keys."](#)

18.1 About Select Keys

A select key is the data found in the burst area when EBB scans the original spool file. It is the text in the areas you select to use as burst or bind criteria. When you select multiple burst areas on a report, the combination of the areas make up one select key. Each time the data changes in any area, the system creates a select key unless it exists already. A select key exists for each unique set of data. For example, if the burst criterion is the company number and there are six companies, there are six select keys.

The system links the select key to the version ID. Burst areas can be the same on any number of reports, in any number of versions. EBB does not create duplicate select keys for a version, but allows duplicates in the software environment. The system assigns and uses an entity number for each select key.

Complete the following tasks:

- Load select keys
- Work with select keys

Load Select Keys

This chapter contains these topics:

- [Section 19.1, "Loading Select Keys,"](#)
- [Section 19.2, "Loading Select Keys for a Single Spool File,"](#)
- [Section 19.3, "Loading Select Keys for Multiple Spool Files."](#)

19.1 Loading Select Keys

When the system loads select keys, EBB scans the original spool report file and stores the data in the select key areas. You can load select keys for reports individually, or load select keys for multiple reports at the same time.

To load select keys, the spool file to be burst must exist.

Navigation

From **Electronic Burst and Bind (G98E)**, choose **Maintain EBB Versions**

19.1.1 What You Should Know About

Select Keys	Description
Displaying select keys	After you load the select keys, you can display them on Maintain EBB Versions by entering 2 next to the version ID.

19.2 Loading Select Keys for a Single Spool File

Load select keys for a single spool file when a version contains only one report or when you add a report to an existing EBB version for which select keys exist.

To load select keys or a single spool file


1. On **Maintain EBB Versions**, enter 1 in the Option field next to the version to which you want to load select keys.
2. On **EBB Reports Selection**, enter 1 in the Option field next to the report.
3. In the **Burst Selection Setup** area, enter 2 for **Spool File Example**.
4. On **Spool File Selection**, enter the output queue name in which the spool file resides in the **OUTQ** field.
5. Enter 7 in the Option field next to the spool file for which you want to load select keys.

Loading can take several minutes.

When loading is complete, the following message displays:

Preload Select Keys have completed. You can see New Select Keys in the last column.

Figure 19–1 Spool File Selection (Select Keys or Spool) screen



6. Exit (F3) until Maintain EBB Versions displays.


19.3 Loading Select Keys for Multiple Spool Files

When your EBB version bursts data from multiple reports, you might want to load the select keys for the spool files at the same time, rather than loading the select keys for spool files individually.

Load select keys for multiple spool files

1. On Maintain EBB Versions enter 5 in the Option field next to the version to which you want to load select keys.
2. On Spool File Selection, enter the output queue in which the spool files reside in the OUTQ field.

Notice that all spool files in the output queue for that version display.

Figure 19–2 Spool File Selection (Load Multiple Spool Files) screen

3. Enter 7 in the Option field next to each spool file and press Enter after each confirmation message.

When loading is complete, the following message displays:

Preload Select Keys have completed. You can see New Select Keys in the last column.

4. Exit (F3) until Maintain EBB Versions displays.

Add Select Keys

This chapter contains the topic:

- [Section 20.1, "Add Select Keys."](#)

20.1 Add Select Keys

Use the Maintain EBB Versions program to add a new select key. After you add the select key, you also use the Maintain EBB Versions to:

- Access Name Search for DREAM Writer reports
- Enter data for a burst area
- Delete select keys

To add a select key


Navigation

From **Electronic Burst and Bind (G98E)**, choose **Maintain EBB Versions**

1. On Maintain EBB Versions enter 2 in the Option field for the version with which you want to work.

The select keys for that version display on Select Key Maintenance.


Figure 20-1 Select Key Maintenance screen



2. Choose and Add Selection Key (F6)

On EBB Select Key Maintenance, enter the select key exactly as you want it to appear on the report in the Select Key field.

Figure 20-2 EBB Select Key Maintenance screen



The Select Key Maintenance screen displays, with the new select key at the bottom of the select key list.

20.1.1 Options

On the Select Key Maintenance form, you can use the following options:

Option	Description
1	View functions that are assigned to the select key. By default, the first function is Print. Until you add or change a routing function, the default Print function is not visible and appears as a blank.
5	Display a Name Search window for DREAM Writer reports. If the select key relates to an Address Book record, this option allows you to verify the address and the A/R, A/P, and Category Codes with the select key.
7	Globally add or change a routing function.
9	Delete select keys and functions. To delete select keys, enter 9 in the Option field next to the keys you want to delete. Be aware that the system deletes routing functions when you delete select keys.

Part VI

Routing Functions

This part contains these chapters:

- [Chapter 21, "Overview to Routing Functions,"](#)
- [Chapter 22, "Create a Routing Function,"](#)
- [Chapter 23, "Delete a Routing Function,"](#)
- [Chapter 24, "Assign Routing Functions to Select Keys,"](#)
- [Chapter 25, "Change Select Key Parameters,"](#)
- [Chapter 26, "Print the Entity/Functions Report."](#)

Overview to Routing Functions

This chapter contains these topics:

- [Section 21.1, "About Routing Functions,"](#)
- [Section 21.2, "What is a Routing Function?,"](#)
- [Section 21.3, "Command Line Entry Requirements,"](#)
- [Section 21.4, "Keywords."](#)

21.1 About Routing Functions

After you create a version, select spool report files, specify the burst area the within file, and preload the select keys, you must assign routing functions to control the final output. JD Edwards World includes routing functions with EBB. You can modify these routing functions for your specific needs or create new routing functions.

To work with routing functions, perform the following tasks:

- Create a routing function
- Delete a routing function
- Assign routing functions to select keys
- Change select key parameters
- Print the entity/functions report

21.2 What is a Routing Function?

A routing function is a print or output instruction, but can be any command that you enter on the command line. You create and assign routing functions to select keys individually or globally. Until you assign a routing function to a select key, the routing function has no functionality.

21.2.1 Demo Routing Functions

JD Edwards World includes three demo routing functions with EBB. During installation, the system compares the names of the demo functions to existing functions. If the name of an existing routing function matches that of a demo function, the existing routing function is not replaced. You can use or modify the demo routing functions.

21.2.2 The PRINT Routing Function

The system assumes PRINT as the default routing function for each Select Key. This function must always be the first function. You can change the out queue and number of copies and assign additional routing functions.

See Also:

- [Appendix B, "Routing Functions,"](#)
- [Chapter 22, "Create a Routing Function"](#) and [Chapter 24, "Assign Routing Functions to Select Keys."](#)

21.3 Command Line Entry Requirements

The system limits routing functions to ten parameters. Some of the command line (CL) entries include more than one variable. There is no limit on the number of CL variables, only the parameters. The system provides four lines for entering the CL command.

Enter the command with the following exceptions:

- The special character & (ampersand) instructs EBB where to insert a parameter. EBB inserts parameters from left to right, starting with parameter 1.
- The special character % (percent) identifies the end of the CL command (% is not necessary on the PRINT function).
- The special character ? (question mark) denotes a blank space in commands which require a blank between two parameters. For example, the TOUSRID keyword in the SNDNETSPLF command requires a blank between the user ID and the address.
- Do not enter more than one blank space between one keyword/parameter combination and the next.

21.4 Keywords

Many functions include parameters that use special keywords. Do not change these keywords, because they identify a spool file to the function.

EBB reserves five keywords, which identify a spool file. They are:

*SPLNUM - Spool File Number

*SPLNAM - Spool File Name

*USER - User ID

*JOBNUM - Job Number

*JOBNAM - Job Name

The system often needs some or all of these parameters for any CL command which operates on spool files.

Note: Some commands, such as the change spool file attribute - CHGSPLFA, do not work if the spool file you want to change is at a writing status. If you are routing burst or bound reports to an output queue that links to an active writer, some of the reports will not reflect any functions except for the first PRINT function. For subsequent functions to process, direct your PRINT function to an output queue that is not for printing. Then use the OUTQ parameter on the CHGSPLFA command to move the PRINT function to an out queue for printing.

Create a Routing Function

This chapter contains these topics:

- [Section 22.1, "Creating a Routing Function,"](#)
- [Section 22.2, "Creating a Routing Function from an Existing Function,"](#)
- [Section 22.3, "Creating a New Routing Function."](#)

22.1 Creating a Routing Function

Navigation

From **Electronic Burst and Bind (G98E)**, choose **Maintain EBB Functions**

Use the **Maintain EBB Functions** program (P98E25) to create a routing function. There are two methods for creating a routing function:

- [Creating a Routing Function from an Existing Function](#)
- [Creating a New Routing Function](#)

You can name a routing function anything except PRINT because JD Edwards World reserves this as the default routing function.

When you create a function, determine if you can use an existing function to create a new function. If not, then create a new one.

22.1.1 What You Should Know About

Parameters	Description
Parameters limit	The system limits the number of parameters for a function to 10. Parameters include banner page, entity/routing ID, output queue, name, and number of copies.
Using & (ampersand) for parameter substitution	For parameter substitution, use a word or code rather than an & (ampersand) because the IBM command editor does not allow the & character.

22.2 Creating a Routing Function from an Existing Function


Before you create a routing function, determine if a similar one exists that you can modify. For example, you can create a PRINT1 function from the PRINT function for the purpose of routing output to another out queue. The command is the same, but the out queue and name are different. If you create new functions from an existing one, JD

Edwards World recommends that you give each a unique name, such PRINT2, PRINT3, and so forth.

To create a routing function from an existing function

1. On Maintain EBB Functions, enter 1 in the Option field of the business function on which you want to base a new function.


Figure 22–1 Maintain EBB Functions screen



2. On EBB - Maintain Function Description, change one or more of the following fields:
 - \Description
 - \Parameters

Note: For an IBM command, enter the command name in the Command String field and choose Prompt on Command String (F4).

Figure 22–2 EBB Maintain Function Description screen



3. Enter up to 10 parameters.
EBB Function Description fields are blank for defining additional functions.
4. Exit (F3) to Maintain EBB Functions.
The new functions display on Maintain EBB Functions.

22.3 Creating a New Routing Function

Create a new routing function when you cannot use an existing function.

To create a new routing function

1. On Maintain EBB Functions, choose Add New Function (F6).
2. On EBB - Maintain Function Description, complete the following fields:
 - \Description
 - \Parameters

Note: For an IBM command, enter the command name in the Command String field and choose Prompt on Command String (F4).

3. Exit (F3) to Maintain EBB Functions.
The new functions display on Maintain EBB Functions.

Delete a Routing Function

Delete a routing function when it is no longer useful. You can delete a function so that it is no longer available or you can delete a function from the select keys.

Note: Do not delete the PRINT function.

This chapter contains these topics:

- [Section 23.1, "Deleting a Routing Function in EBB,"](#)
- [Section 23.2, "Deleting a Routing Function from Select Keys."](#)

23.1 Deleting a Routing Function in EBB

Delete a routing function if you are sure that it is no longer necessary. After you delete the routing function, you cannot recover the function.


Navigation

From **Electronic Burst and Bind (G98E)**, choose **Maintain EBB Functions**

To delete a routing function from EBB

1. On **Maintain EBB Functions**, enter 1 in the **Option** field next to the routing function you want to delete.
2. On **EBB - Maintain Function Description**, choose **Delete**.

Figure 23-1 EBB Maintenance Function Description (Delete Routing) screen



3. Exit (F3) to Maintain EBB Functions.
The routing function no longer appears in the list.

23.2 Deleting a Routing Function from Select Keys

Use this procedure to only delete the function from specific select keys.

Navigation


From Electronic Burst and Bind (G98E), choose Maintain EBB Versions

To delete a routing function from select keys

1. On Maintain EBB Versions, enter 2 in the Option field next to the version that contains the routing function that you want to delete.
2. On Select Key Maintenance, enter 7 in the Option field of the select keys from which you want to delete a routing function.

The functions that are attached to the first select key appear on Entity/Function Maintenance Global.

Figure 23-2 Entity/Function Maintenance screen



3. Enter 9 in the Option field next to the appropriate routing functions.

Assign Routing Functions to Select Keys

This chapter contains these topics:

- [Section 24.1, "Assigning Routing Functions to Select Keys,"](#)
- [Section 24.2, "Assigning the PRINT Routing Function,"](#)
- [Section 24.3, "Assigning a Routing Function to a Single Select Key,"](#)
- [Section 24.4, "Assigning a Routing Function to Multiple Select Keys."](#)

24.1 Assigning Routing Functions to Select Keys

After you create a routing function, you must assign the function to one or more select keys. When you run a version, EBB processes the command string logic of the function that is assigned to the select keys. Unless you assign a function to a select key, it has no functionality.

For each select key, you must assign the PRINT routing function first. You cannot assign another routing function until you assign the PRINT function to the select key. You can only assign one routing function at a time.

Use the Maintain EBB Versions program (P98E10) to assign routing functions. Assign a routing function to a single select key or multiple select keys.

To assign a routing function, perform the following:

- Assigning the PRINT Routing Function
- Assigning a Routing Function to a Single Select Key
- Assigning a Routing Function to Multiple Select Keys

Navigation

From **Electronic Burst and Bind (G98E)**, choose **Maintain EBB Versions**

24.1.1 Before You Begin

- You must define the burst area of the spool report file and preload the select keys.


24.2 Assigning the PRINT Routing Function

The first time you assign a routing function to a select key, EBB confirms the assignment of the PRINT routing function. You must assign the PRINT routing function to the select key before assigning any other functions.

To assign the PRINT Routing Function


1. On Maintain EBB Versions, enter 2 in the Option field of the applicable version.
The select keys for the version display on Select Key Maintenance. When a function is assigned, an asterisk (*) displays next to select key.

Figure 24-1 Select Key Maintenance (PRINT Routing) screen



2. Review whether any function has been assigned to the select key with which you want to work.
If an asterisk displays, you do not need to continue because the PRINT function is assigned to the select key.
3. On Select Key Maintenance, enter 1 in the Option field of the applicable select key.


Figure 24–2 Entity/Function Maintenance (PRINT Routing) screen



4. Choose Add Function (F6).

The PRINT function parameters display on Entity/Function Params Maintenance.


Figure 24–3 Entity/Function Parameters Maintenance screen



5. Press Enter, and then Exit (F3) this screen.

The PRINT function displays on Entity/Function Maintenance.

Figure 24-4 Entity/Function Maintenance (PRINT Displayed) screen



24.3 Assigning a Routing Function to a Single Select Key

To assign a routing function, determine the output queue to which you want to route a select key.


24.3.1 Before You Begin

- If the PRINT routing function is not assigned to the select key with which you want to work, you must first assign the PRINT routing function.

To assign a routing function to a select key


1. On Maintain EBB Versions, enter 2 in the Option field of the applicable version.
2. On Select Key Maintenance, enter 1 in the Option field of the applicable select key.

Figure 24–5 Select Key Maintenance (Select Key) screen




3. On Entity/Function Maintenance, choose Add New Function For Entity (F6).

Figure 24–6 Entity/Function Maintenance (Add New) screen




4. On Entity/Function Parm Maintenance, choose Functions (F4).

Figure 24-7 Entity/Function Parameters Maintenance (Functions) screen




5. On Function Selection, enter 4 in the Option field next to the appropriate routing function.

Figure 24-8 Function Selection screen



The function parameters display on Entity/Function Params Maintenance.

Figure 24–9 Entity/Function Parameters Maintenance (Displayed) screen




6. Accept the defaults or modify any of the following fields:

- \Print Banner Page
- \Parameters

7. Exit (F3) to Entity/Function Maintenance.


The additional routing function displays with other routing functions that are attached to the select key.

Figure 24–10 Entity/Function Maintenance (Added Function) screen



8. Exit (F3) to Select Key Maintenance.
An * displays next to the select key, indicating a successful function assignment.

Figure 24–11 Select Key Maintenance (* Displayed) screen



24.4 Assigning a Routing Function to Multiple Select Keys

If you want to assign a routing function to multiple keys, assign the function globally rather than to each select key individually.

24.4.1 To assign a routing function to multiple select keys

1. On Maintain EBB Versions, enter 2 in the Option field of the applicable version.
2. On Select Key Maintenance, enter 7 in the Option field of the select keys to which you want to assign a routing function.
3. On Entity/Function Maintenance - Global, choose Add Function (F6).
4. On Entity/Function Parms Maintenance Global, choose Functions (F4).
5. On Function Selection, enter 4 in the Option field next to the appropriate routing function.

The function parameters display on Entity Function Parms Maintenance Global.

6. Accept or modify any of the following fields and press Enter:
 - `Print Banner Page
 - `Parameters
7. Exit (F3) to Entity/Function Maintenance Global.

The additional routing function displays with other routing functions that are attached to the select key.

Change Select Key Parameters

This chapter contains the topic:

- [Section 25.1, "Changing Parameters for a Select Key."](#)

25.1 Changing Parameters for a Select Key

Use the Select Key Maintenance program (P98E20) to customize the parameters for a routing function or a select key. For example, depending on the select key you can customize the PRINT routing function to change the number of copies or specify an output queue.

The EBB version ID, select key and routing ID appear on the banner page. You can also access Select Key Maintenance to:

- Change the banner page for a print function on a select key
- Change the entity/routing ID for any print function.

Do not change certain keywords. See [Section 21.4, "Keywords"](#) for a list of keywords you should not change.

To change parameters for a select key


Navigation

From **Electronic Burst and Bind (G98E)**, choose **Maintain EBB Versions**

1. On **Maintain EBB Versions**, enter 2 in the Option field for the appropriate version.
2. On **Select Key Maintenance**, enter 1 in the Option field for the appropriate select key.


Due to screen size limitations, only the first five parameters for a routing function display.

Figure 25–1 Entity/Function Maintenance (Change Parameters) screen



3. On Entity/Function Maintenance, enter 2 in the Option field to view up to ten parameters for a function.

Figure 25–2 Entity/Function Parameters Maintenance (Option) screen



4. Edit the parameters as necessary and press Enter.
5. Exit (F3) to Select Key Maintenance.

Print the Entity/Functions Report

This chapter contains the topic:

- [Section 26.1, "Printing the Entity/Functions Report."](#)

26.1 Printing the Entity/Functions Report

The Entity/Functions Report contains information for all Version IDs. The report displays the following:

- Entity keys (a unique number for the select key)
- Select keys
- Routing functions that are attached to select keys

To print the entity functions report

Navigation

From Electronic Burst and Bind (G98E), choose Entity/Functions Report

The report request submits to batch.

Part VII

Substitute Select Keys

This part contains these chapters:

- [Chapter 27, "Overview to Substitute Select Keys,"](#)
- [Chapter 28, "Define Substitute Select Keys,"](#)
- [Chapter 29, "Generate the Cross-Reference Index,"](#)
- [Chapter 30, "Update the Cross-Reference Table."](#)

Overview to Substitute Select Keys

This chapter contains the topic:

- [Section 27.1, "About Substitute Select Keys."](#)

27.1 About Substitute Select Keys

The process of bursting and binding depends on specific criteria being on the report. However, you might be working with a report that does not contain the specific information you want on the report. Rather than modifying the report and generating a new spool file that includes the required information, you can define substitute select keys.

When you burst reports that use substitute select keys, EBB uses the original and substitute select keys. The system uses substitute select keys as if they were on the report originally.

Use substitute select keys to burst and bind reports when:

- Information on which you want to burst on is not in the report
- Information between two reports relates, but is not identical, and you must match this to bind the reports together
- Select keys, both the original and substitute, exist in any one file

Substitute select keys require a cross-reference table, between the original and substitute select keys, before EBB can burst a report. Any EBB version can refer to any table. You can reference multiple reports within multiple versions, that burst using the same original and substitute select key combinations, to the same cross reference table. To more easily distinguish one burst report from another, print the substitute select key on the reports.

This section includes the following tasks:

- Define substitute select keys
- Generate the cross-reference index
- Update the cross-reference table

27.1.1 Examples Using Substitute Select Keys

The following are examples of how you can use substitute select keys to bind reports. Both examples use the same cross reference table.

Example 1

In this example, EBB binds reports based on criterion that is not in the spool file.

- A company organizes business units into divisions, with multiple business units in each division. A report runs by business unit each month using fifteen different DREAM Writer versions. Each DREAM Writer version generates a report for a specific division. The business unit number prints on the report, but the division code does not. EBB distributes the reports to the managers of each division.
- The substitute select key option allows you to run the report once, selecting all fifteen divisions. Then EBB bursts the report by division and routes the reports to the appropriate division managers.

To accomplish this, a cross reference table must exist between the business unit number and the division code. The division code is the substitute select key. The substitute select key links the cross reference table to the EBB version.

Example 2

In this example, two reports are bound. The data the system uses is not on one of the reports.

- Report 1 contains all expenses in each business unit. Report 2 contains sales in each division. The division code is not on Report 1, but the company wants to distribute both reports to the division managers.
- The substitute select key option allows you to bind two reports, even when the information the system needs for binding is not on both reports. To enable EBB to burst the sales and expenses reports by division, and route to the appropriate division managers, you must add a substitute select key for the division code to Report 1. The cross reference table provides the link between the business unit (the original select key) and the division code (the substitute select key). The division code is defined in Report 2 and requires only the setup of the division code as the select key on the report.

Define Substitute Select Keys

This chapter contains the topic:

- [Section 28.1, "Defining Substitute Select Keys."](#)

28.1 Defining Substitute Select Keys

You can attach a substitute select key before or after you generate a cross reference table.

If you want to change the substitute select key, change the name of the cross reference table to which the version links. You can also update the cross-reference table or change the print instructions for the substitute select key.


To define a substitute select key

Navigation

From **Electronic Burst and Bind (G98E)**, choose **Maintain EBB Versions**

1. On **Maintain EBB Versions**, enter 1 in the **Option** field for the appropriate version.
If a substitute select key exists for a report, **SK** appears next to the report description on **EBB Reports Selection**.
2. On **EBB Reports Selection**, enter 2 in the **Option** field.


Figure 28–1 *Substitute Key Maintenance screen*



3. On **Substitute Key Maintenance**, complete the following fields:
 - `Table Number

- `Literal to Print
 - `Print Position
4. `Exit (F3) the window.

Figure 28–2 EBB Reports Selection (Substitute) screen



The select key displays with the notation SK on EBB Reports Selection.

Field	Explanation
Rebuild cross-reference	Enter N for no.
Table number	The name (up to ten characters) of the table the user creates in which the original key and substitute select keys are cross referenced. This field is required
Print substitute key	Enter either Y or N to indicate whether the substitute select key should be printed on the final output. This field is required.
Literal to print	If you want to print the substitute select key on the report, enter up to ten characters for a header. The text appears on the left side of the substitute select key. Since a blank is inserted after the literal, it actually occupies 11 spaces on the report.
Print row	The row on which you want the substitute select key to appear. This field is mandatory if the Print Substitute Key? field is set to Y. Use a number between 1 and 99. If a literal has been entered, it will print to the left of the substitute select key. Choose an area on the report where important information will not be overlaid.
Print position	The position in which the literal (if entered) and substitute select key will begin to print. This field is required if the Print Substitute Key? field is set to Y. Use a number between 1 and 191.

Field	Explanation
Print length	The combined length of the literal (if entered) and a blank space plus the substitute select key that will appear on the report. This field is required if the Print Substitute Key? field is set to Y. Use a number between 1 and 191.

Generate the Cross-Reference Index

This chapter contains the topic:

- [Section 29.1, "Generating the Cross-Reference Index."](#)

29.1 Generating the Cross-Reference Index

After you define one or more substitute select keys, you must generate a cross-reference index in preparation for updating the substitute select key table.

Generate the cross-reference index when you:

- Define a new substitute select key
- Change a substitute select key
- Encounter problems updating the substitute select key table

Note: Generating the cross-reference index can take a considerable amount of time to run and you should run this during non-business hours.

After you generate the cross-reference index, you must then create a cross-reference table of the substitute select key data.


To generate the cross-reference index

Navigation

From **Rebuilds and Global Updates (G9642)**, choose **Cross-Ref Index**

Choose **Execute (F6)**.

Figure 29-1 Rebuild Cross Reference screen



Update the Cross-Reference Table

After you generate a cross-reference index for substitute select keys, you must update the table that cross-references the data for the substitute select keys. EBB uses the cross-reference table of data to burst reports.

Any EBB version can refer to any table. You can reference multiple reports within multiple versions that burst using the same original and substitute select key combinations, to the same cross-reference table. To distinguish one burst report from another, print the substitute select key on the reports.

To update a substitute select key cross-reference, you must set up a version of a form for each cross-reference table. You set up a cross-reference table using a DREAM Writer version with form P98E08 for each cross-reference table.

This chapter contains these topics:

- [Section 30.1, "Before You Begin,"](#)
- [Section 30.2, "Adding a DREAM Writer Report Version for P98E08,"](#)
- [Section 30.3, "Identifying the Version,"](#)
- [Section 30.4, "Defining Version Parameters,"](#)
- [Section 30.5, "Specifying Processing Option Revisions,"](#)
- [Section 30.6, "Selecting Data,"](#)
- [Section 30.7, "Assigning Sequence Numbers to Select Keys."](#)

30.1 Before You Begin

- Ensure you are familiar with the reports, version, and file information.
- You must be familiar with DREAM Writer.
- A current cross-reference index must exist.

30.2 Adding a DREAM Writer Report Version for P98E08

You must add a version of Form P98E08 for each cross-reference table prior to processing the EBB version.


Navigation

From DREAM Writer (G81), choose **Version List**

To add a DREAM Writer report version for P98E08


1. On Versions List, enter P98E08 for the Form field.

Figure 30–1 Version List screen



2. Enter 3 in the Option field for the appropriate version.

Figure 30–2 Dream Writer Version Copy screen



3. On Dream Writer Version Copy, complete the following field:
 - \`Continue by completing the steps for Identifying the Version.


Field	Explanation
Form	This form name is the name of the RPG program which controls the function format of this DREAM Writer report. For FASTR and P & E FASTR reports, the form name can normally be any name the users may create.

30.3 Identifying the Version

Use the Version Identification screen to:

- Identify a report title for the Versions List. Enter a version title that is meaningful.
- Specify up to three report titles to display on the hard copy of the report.
- Indicate the language based on a user defined code. The system uses the language on screens and printed reports.

Figure 30–3 Version Identification screen



On Version Identification, complete the following fields:

- Language
- Version Title
- Optional Report Title

Continue by completing the steps for Defining Version Parameters.

Field	Explanation
Language	<p>A user defined code (01/LP) that specifies a language to use in screens and printed reports.</p> <p>For World, if you leave the Language field blank, the system uses the language that you specify in your user preferences. If you do not specify a language in your user preferences, the system uses the default language for the system.</p> <p>Before any translations can become effective, a language code must exist at either the system level or in your user preferences.</p> <p><i>Screen-specific information</i></p> <p>A user defined code that specifies the language used for the title of this version. The allowed values are found in system 01, user defined code type LP.</p>

Field	Explanation
Version Title	A description of the version that appears next to the version number. The version title is different from the report title.
Optional Report Title	The title that appears at the top of the report. It can include up to three lines with 40 characters each. The lines are automatically centered on the report.

30.4 Defining Version Parameters


Additional Parameters contains various job control parameters.

To define version parameters

On Additional Parameters, complete the following field:

- Based on File
 - The Based on File field must be the file that contains the original select keys and the substitute select keys.

Figure 30–4 Additional Parameters screen



Note: If you change the based on file, you might need to delete and add the data sequence setup records so that the system associates the correct file name with the internal keys.

Continue by completing the steps for Specifying Processing Option Revisions.

Field	Explanation
Based on File	Identifies the name of the physical file on which a logical file is based. In DREAM Writer, the based on file refers to the file on which all operations, such as Data Selection, Data Sequence, and so forth are to be done. <i>Screen-specific information</i> The file on which Data Selection and Data Sequence are done.

30.5 Specifying Processing Option Revisions


Processing Options Revisions identify the table number to which you assign the substitute select key table.

To specify processing options for substitute select key table

On Processing Options Revisions, enter the table number for the substitute select key table.

Name this table logically.

Figure 30–5 Processing Options Revisions screen



30.5.1 Processing Options

See [Chapter 38, "Electronic Burst and Bind Processing Option."](#)

30.6 Selecting Data

Because substitute select keys do not use data selection, press Enter without selecting any data.

30.7 Assigning Sequence Numbers to Select Keys

You use the Data Sequence Set Up screen to locate the field that represents the original select key.

When you assign sequence numbers to select keys, you use a different range of numbers than the original select key so that you can distinguish the original from the substitute select key. For example, if you are updating the cross-reference table to use the region code as the original select key and the group code as the substitute select key, enter the sequence number 001 next to the region. On the group code, enter the sequence number 100 and change the Option field to Y (yes).

To assign sequence numbers to select keys


1. On Data Sequence Set Up, enter a number in the Sequence field for the original select key.

If there are multiple fields that make up the original select key, assign all fields a sequence number in the appropriate order, from left to right.

2. Ensure that the original select key fields contain an N (no) in the Option field.

Do not press Enter.

Figure 30–6 Data Sequence Set Up screen



3. Enter a different range of numbers in the Sequence field for the substitute select key.

Do not press Enter.

4. To identify the substitute select key fields, enter Y in the Option field.
5. Press Enter.
6. Run the DREAM Writer version.

30.7.1 Function Exits

Use these functions on the Data Sequence Set Up screen to perform the following tasks:

- More Display (F4)
- Update with redisplay (F4)
- Display all data fields (F16)

Part VIII

Monitor

This part contains these chapters:

- [Chapter 31, "Overview to Monitor,"](#)
- [Chapter 32, "Move Spool Files to EBBSTART,"](#)
- [Chapter 33, "Start the Monitor,"](#)
- [Chapter 34, "End the Monitor,"](#)
- [Chapter 35, "Display the EBB Message Queue,"](#)
- [Chapter 36, "Clear the EBB History Log,"](#)
- [Chapter 37, "View the EBB Process Report."](#)

Overview to Monitor

This chapter contains this topic:

- [Section 31.1, "About the Monitor."](#)

31.1 About the Monitor

The monitor is a program that bursts, binds, and routes spool files for the versions you set up. The monitor does not run continually. The monitor uses a built in delay interval during which time the monitor is inactive. After the delay interval (usually 60 seconds), the monitor becomes active. When the monitor is running, the monitor evaluates each spool file in the EBBSTART output queue to determine if it should process the file. If all criteria are met, the monitor processes the spool file. If criteria are not met, the monitor generates a message. You can view these messages in the EBB message queue.

You use the EBB Setup File Maintenance program (P98E94A) to govern basic guidelines for all EBB versions on your system. The program contains the monitor delay interval time, job queue, output queues, and other default information. You set up the EBB Setup File Maintenance program during the EBB installation and you can modify this file as necessary.

To work with the EBB Monitor, complete the following tasks:

- Move spool files to EBBSTART
- Start the monitor
- End the monitor
- Display the EBB message queue
- Clear the EBB history log
- View the EBB process report

31.1.1 Before You Begin

Review the following checklist to ensure that the monitor runs successfully.

- The spool file must exist. If you do not want the monitor to process the spool file immediately, create the spool file in an output queue other than EBBSTART. Then move the spool file to EBBSTART when you want to process the spool file.
- If you create spool files initially in an output queue other than EBBSTART, change the spool file output queue to EBBSTART when you are ready to burst the spool file.

- The User Data attribute on the spool file must be identical to the version ID name.
- The spool file must be in RDY status.
- All version spool files must be present.
- The burst selection criteria must not exceed 90 characters. You can select multiple rows on which to burst as long as the total burst criterion does not exceed 90 characters.

Move Spool Files to EBBSTART

This chapter contains the topic:

- [Section 32.1, "Moving Spool Files to EBBSTART."](#)

32.1 Moving Spool Files to EBBSTART

When you are ready to burst a report, ensure that it is in the output queue, EBBSTART. If the spool files are in an output queue other than EBBSTART, you must change the output queue to EBBSTART.

To move spool files to EBBSTART

Navigation

From **Electronic Burst and Bind (G98E)**, choose **Maintain EBB Versions**

1. On **Maintain EBB Versions**, enter 5 in the **Option** field next to the version to which you want to move the spool files.
2. On **Spool File Selection**, enter the output queue in which your spool files reside in the **OUTQ** field.
3. Enter 2 in the **Option** field for the first file.

The file no longer displays on the screen because it is now in the EBBSTART output queue.

Repeat the previous step for each spool file. After you move all files in the output queue to the EBBSTART output queue, the following message displays:

Version (Version ID) report was not found in this OUTQ

4. Enter EBBSTART in the **OUTQ** field and press **Enter**.

The spool files display.

Start the Monitor

This chapter contains the topic:

- [Section 33.1, "Starting the Monitor."](#)

33.1 Starting the Monitor

The monitor processes spool files in the EBBSTART output queue with a status of RDY, where the User Data attribute is identical to the version ID. The monitor delay time that you specify during setup determines how often the monitor becomes active to process spool files.

Restart the monitor when it ends abnormally. When the monitor ends abnormally, the indicators that the start program uses are not automatically reset and you must restart the monitor.

33.1.1 Before You Begin

- Ensure that the monitor is not currently active. If the monitor is running and you want to interrupt it to perform other processes, you must end the monitor.

Navigation

From Electronic Burst and Bind (G98E), choose **Start EBB Monitor**

33.1.2 What You Should Know About

Topic	Description
Automatically starting and stopping the EBB monitor	You can use Sleeper to automatically start the EBB monitor. You must set up Sleeper to access J6000 to start the monitor. SVR records for J6000 must exist in the system. Set up Sleeper to submit the programs to a non-EBB job queue.

This chapter contains the topic:

- [Section 34.1, "Ending the Monitor."](#)

34.1 Ending the Monitor

Navigation

From **Electronic Burst and Bind (G98E)**, choose **End EBB Monitor**

Because spool files automatically process at a specific time, you might need to end the monitor to perform other processes or when reports are not processing. When you end the monitor, EBB becomes inactive and does not process spool files. You must then start the monitor.

End the monitor when you want to:

- Clear the monitor before adding a new version. Clearing the monitor deletes all spool files.
- Backup files EBB uses.
- Change a version or select key.
- Restart the monitor.

Note: Even though the monitor may be inactive, the indicators are reset when you end the monitor.

To end the monitor

1. After you choose **End EBB Monitor**, choose **Display EBB Message Queue**.

On **Display Messages**, the follow message displays:

EBB monitor ended

2. Exit (F3) the message queue.

34.1.1 What You Should Know About

Topic	Description
Automatically end the EBB monitor	You can use Sleeper to automatically end the EBB monitor. You must set up Sleeper to access J6001a to end the monitor. SVR records for J6001a must exist in the system. Set up Sleeper to submit the programs to a non-EBB job queue.

Display the EBB Message Queue

This chapter contains the topic:

- [Section 35.1, "Displaying the EBB Message Queue."](#)

35.1 Displaying the EBB Message Queue

The monitor writes messages to the EBB message queue for the following reasons:

- Versions with multiple spool files are not in the EBBSTART output queue with a RDY Status
- Reports do not contain burst criteria
- Reports in EBBSTART have an invalid version ID

Rather than receiving all messages, you can specify a message severity level that filters the types of messages the system writes to the EBB Message Queue.

The system writes each message only once. If the monitor becomes active after a delay, it will not write the same message again. The monitor checks the message queue to verify if the message exists before writing it again.


To display the EBB Message Queue

Navigation

From **Electronic Burst and Bind (G98E)**, choose **Display EBB Message Queue**

On **Display Messages**, review the messages and press **Enter**.

Figure 35-1 *Display Messages screen*



35.1.1 Function Keys

Use the Function keys to perform the following tasks:

- F11 removes a message on the line where the cursor appears.
- F10 displays all messages. This includes messages regarding the starting and ending of the monitor, such as the time, date and by whom. These messages are repeated each time you start and end the monitor.
- F16 removes all messages. Be certain to do this occasionally, especially if a large number of files are pending for the system to process.

See Also:

- [Appendix C, "EBB Messages"](#) for a complete list of messages and corresponding severity levels.

Clear the EBB History Log

This chapter contains the topic:

- [Section 36.1, "Clearing the EBB History Log."](#)

36.1 Clearing the EBB History Log

EBB maintains a history log of information on report distribution in the EBB Audit Log File (F6004). The EBB Audit Log File contains a record of every function for each spool file the monitor processes, similar to a cumulative process report for all versions.

The EBB History Log includes:

- Type of processing. The EBB monitor programs enter this information when the spool files generate. They include attached Parameter, Default or Error.
- Select key
- Output queue
- Output library name
- Output spool file name
- Sequence number
- Processing date and time
- User ID
- Job name/number
- Version ID

Because this file can quickly become very large, JD Edwards World recommends that you clear the log file periodically. You clear the log through a specific date.


To clear the EBB History Log

Navigation

From **Electronic Burst and Bind (G98E)**, choose **Clear History Log**

1. Enter the date through which you want to clear the history log in the format of MMDDYY and click Enter.

Figure 36-1 Clear History Log screen



The following message displays:

Parameters OK - press F10 to continue

2. Choose Delete History (F10).

View the EBB Process Report

This chapter contains the topic:

- [Section 37.1, "Viewing the EBB Process Report."](#)

37.1 Viewing the EBB Process Report

Each time the monitor processes reports, it generates a process report in the EBBFINAL output queue. Even if you route the reports to another output queue, EBBFINAL receives the process report. This report is the EBB Spool File Routing Report (R98E04).

The process report indicates a status of HLD which allows you to determine whether to view or print the report. It reflects one of the following messages:

- Routed other than to Default
- Routed to Default Outq
- Routed to Error Outq

The report prints totals for the number of select keys with a print routing function, the number of reports sent to the default output queue you set up, and the number of reports sent to an error output queue because new select keys were found when bursting the report.

The error output queue contains reports burst with no routing instruction. For example, you add a new business unit to a report after you set up the original report in EBB. Because no select key exists for that business unit, you must add a select key or preload select keys before you burst to correct the report.

The Enter column might contain the following letters:

- P - indicates that routing functions exist.
- D - designates the default output queue.
- E - specifies the error output queue. Notice that the OUTQ column displays the name of the output queue.

Electronic Burst and Bind Processing Option

This chapter contains the topic:

- [Section 38.1, "EBB-Substitute Keys Demo \(P98E08\)."](#)

38.1 EBB-Substitute Keys Demo (P98E08)

Processing Option	Processing Options Requiring Further Description
-------------------	--

Enter the table number for this group of Substitute Keys.

Tips and Techniques

This appendix contains these topics:

- [Section A.1, "Display the JD Edwards World Release Level,"](#)
- [Section A.2, "Override Same Spool File Names with % Menu,"](#)
- [Section A.3, "Correct Inconsistent Page Breaks on FASTR Reports,"](#)
- [Section A.4, "Print and Hold a Spool File,"](#)
- [Section A.5, "Change the Form Type,"](#)
- [Section A.6, "Change User Data Attributes,"](#)
- [Section A.7, "Perform Duplex Printing,"](#)
- [Section A.8, "Send Spool Files Across Network,"](#)
- [Section A.9, "Troubleshooting Tips."](#)

A.1 Display the JD Edwards World Release Level

Choose Product Information from the Help menu.

Alternatively, on the command line, type DSPJDELVL and press enter.

A.2 Override Same Spool File Names with % Menu

In EBB each spool file needs a uniquely name. On batch job submissions, such as a % menu, use the Printer File Override and the Spool File Name options to override the identical spool file names these batch jobs produce.

A.3 Correct Inconsistent Page Breaks on FASTR Reports

The header pages for some FASTR reports might be inconsistent, which is an issue when EBB compares the header pages for bursting and binding. To resolve this, you can code the programs to display the page break data on the top left of each page of a report.

If you experience inconsistent header pages that EBB must use to burst and bind reports, contact the JD Edwards World response line. Differences in software versions may require additional assistance to apply these program changes.

A.4 Print and Hold a Spool File

Create a routing function, HOLDFILE, using the following command:

```
HLDSPFL FILE(&) JOB(&/&/&) SPLNBR(*ONLY) OPTION(*IMMED)%
```

A.5 Change the Form Type

Create a routing function, CHGFORMTYPE, using the following command:

```
CHGSPLFA FILE(&) JOB(&/&/&) SPLNBR(&) FORMTYPE(&)%
```

The FORMTYPE can be hard coded in Parm 6. JD Edwards World reserves the first five parms.

A.6 Change User Data Attributes

Create a routing function, CHGUSRDTA, using the following command:

```
CHGSPLFA FILE(&) JOB(&/&/&) SPLNBR(&) CHGUSRDTA(&)%
```

A.7 Perform Duplex Printing

Add the DUPLEX routing function to the Select Key as follows:

```
CHGSPLFA FILE(&) JOB(&/&/&) SPLNBR(&) DUPLEX(*YES)%
```

A.8 Send Spool Files Across Network

You can use the SNDNETSPL FILE command to send spool files from one AS/400 in a network to another AS/400. The question mark between the two positional parameters for the TOUSRID key word is a place hold to reserve a blank space which the system requires for the key word format.

```
SNDNETSPLF FILE(&) TOUSRID(&?&) JOB(&/&/&)%
```

A.9 Troubleshooting Tips

- Ensure that all the spool files are in the EBBSTART queue. To verify this, enter WRKOUTQ EBBSTART on the command line.
- Ensure that all the spool files you want to generate are in RDY status in the OUTQ. Enter 6 in the Option field to release the file from a hold status, if necessary.
- Ensure you start the EBB monitor. To verify this, review the messages on Display Messages. Choose Display EBB Message Queue from the Electronic Burst and Bind Menu (G98E). If you need to start the EBB monitor, choose Start EBB Monitor on the Electronic Burst and Bind Menu (G98E).
- Ensure that the select keys in are in a consistent location on each page of the report.
- Ensure that you load the select keys prior to running the version. See [Chapter 19, "Load Select Keys"](#) for more information.
- Verify that there are no reports in the EBBERRQ. If so, troubleshoot as necessary.
- Ensure that the Version ID's on the Maintain EBB Versions screen are the same as those in the EBBSTART queue.

- Ensure that the DREAM Writers do not have cover pages. If they do, disable that option.

Routing Functions

JD Edwards World includes the following routing functions in the EBB software. You can modify any of the business functions as necessary.

Routing Function	Description
DUPLEX	Change spool file option for duplex to Y (yes)
FORMTYPE	Change spool file form type by entity
PRINT	Change OUTQ and copies for print

JD Edwards World recommends that you add the following functions using the change spool file attribute command, CHGSPLFA.

Function	Description
COPYF	Copy spool file
FORM	Change spool file form type
FORM400	Change spool file form type to FORM400
HOLDFILE	Hold spool file
PRTSAV	Save spool file



C

EBB Messages

This list contains Electronic Burst and Bind messages along with the level of severity and message text for each.

Message ID	Severity	Message Text
EBB0002	0	Last Record is Displayed
EBB0003	0	First Record is Displayed
EBB0004	10	Invalid Library, File, or Member Name
EBB0005	10	Valid Library Name Required
EBB0006	10	Valid Source File Name Required
EBB0007	10	Valid Member Name Required
EBB0008	10	Valid Output Queue Required
EBB0009	0	Parameters OK - press F10 to continue
EBB0010	10	AS/400 Model Number not found in program table
EBB0011	10	AS/400 Model Serial Number contains an invalid character
EBB0013	10	Customer Number not found on Address Book
EBB0014	0	Software Authorization has been logged
EBB0016	10	First-Time Installation must be Y or N
EBB0017	10	At least one library must be specified to contain EBB data files
EBB0018	10	At least one library must be specified containing the JD Edwards World setup files
EBB0019	0	Report Finished Successfully
EBB0020	10	Report DID NOT FINISH
EBB0021	0	Report Cancelled at User Request
EBB0022	10	Alpha or Date Sequence must be A or D
EBB0023	10	Re-install Backup response must be Y or yes or N for no
EBB0024	10	JD Edwards World Object Library must be specified
EBB0026	10	Target Release is not valid

Message ID	Severity	Message Text
EBB0027	10	Invalid Row. Row must be between 1 and 57
EBB0028	10	Invalid Column. Column must be between 1 and 198
EBB0029	10	Routing Description Invalid
EBB0030	10	Invalid Length Entered Length Must be Greater Than Zero For An ADD
EBB0031	10	Total Key Length Cannot Exceed 90 Positions
EBB0032	10	Invalid Delete, There are no records to be deleted
EBB0033	10	Sequence number already in use You may not duplicate sequence numbers
EBB0034	10	The key length selected can not be less than zero
EBB0035	10	Burst criteria must be on the same row
EBB0040	0	Preload Select Keys Is Running Please be patient
EBB0041	0	Pre Load Select Keys Has Completed, And Found xxx New Select Keys
EBB0042	10	Version xxx report xxx was not found in this OUTQ
EBB0043	10	Select Key Can Not Be Blank
EBB0044	10	Install to Separate Environment must be 'Y' or 'N'
EBB0045	10	Library not found Please check
EBB0046	10	EBB object library was found, and an initial install was requested Please check
EBB0047	10	EBB object library was not found, and a re-install was requested Please check
EBB8000	10	All reports for version: xxx must be in OUTQ EBBSTART and in Ready Status
EBB8001	20	No Functions Found For Version ID: xxx
EBB8003	10	EBB Spool File Not In Ready Status For Version ID
EBB8004	0	No EBB version found for spool file with userdata
EBB8005	10	Error in the Substitute Select Key process (See second level text)
EBB8006	10	Error in the Substitute Select Key process (See second level text)
EBB8007	10	Error in the Substitute Select Key process (See second level text)
EBB8008	10	Rebuild Cross Reference must be 'Y' or 'N'
EBB8009	10	If Rebuild is yes, a DREAM Writer Version must be entered
EBB8010	10	Table Name must be entered

Message ID	Severity	Message Text
EBB8011	10	Enter a 'Y' or 'N' in the Print Key field
EBB8012	10	Print Row must be between 1 and 99
EBB8013	10	Print Position must be between 1 and 191
EBB8014	10	Print Length must be between 1 and 191
EBB8015	10	Date is not valid Please check
EBB8900	10	Invalid Version ID entered
EBB9000	0	EBB monitor started at [time] on [date] by [xxx]
EBB9001	0	EBB monitor ended at [time] on [date] by [xxx]
EBB9002	10	The EBB Monitor is Already Active
EBB9801	20	F0090 was not found in any of the selected common libraries
EBB9802	20	F9200 was not found in any of the selected common libraries
EBB9803	20	F9220 was not found in any of the selected common libraries
EBB9804	20	F9601 was not found in any of the selected common libraries
EBB9805	20	F9611 was not found in any of the selected common libraries
EBB9806	20	F9620 was not found in any of the selected common libraries
EBB9807	20	F9621 was not found in any of the selected common libraries
EBB9808	20	F9801 was not found in any of the selected common libraries
EBB9809	20	F98301 was not found in any of the selected common libraries
EBB9810	20	F0020 was not found in any of the selected common libraries
EBB9811	20	F9800 was not found in any of the selected common libraries
EBB9900	0	EBB Software Installation Completed Successfully
EBB9904	10	Library EBBLIB already exists - reinstall not requested
EBB9905	10	Library EBBLIB does not exist - reinstall requested
EBB9906	0	EBB Create Demo Tape finished successfully
EBB9907	10	EBB Demo Tape Create DID NOT COMPLETE
EBB9908	0	EBB Create Demo Tape cancelled by user request
EBB9909	10	Library specified for the JD Edwards World object library does not exist
EBB9910	10	System Code 60 is already in use on your system

Message ID	Severity	Message Text
EBB9912	10	Delay Time may not be zero or negative
EBB9913	10	EBB JOBQ Name may not be left blank
EBB9914	10	Invalid JOBQ Specified
EBB9915	10	Invalid Receiving OUTQ
EBB9916	10	Invalid Error OUTQ
EBB9917	10	Invalid Default JD Edwards World Dream Writer Source Library
EBB9918	10	Invalid JD Edwards World Dream Writer Source File
EBB9919	10	Invalid Function
EBB9920	10	Duplicate Version ID
EBB9921	10	You Must Enter A Version ID
EBB9922	10	You Must Enter A Version Description
EBB9923	10	Invalid Selection Must Be (Y,N)
EBB9924	10	The Demo Reports may not have loaded correctly
EBB9931	10	Auxiliary Storage Pool must be 1 - 16
EBB9932	0	EBB data file library xxx created
EBB9933	0	EBB data area EBBFIL# created in library xxx
EBB9934	0	EBB data area QEBB created in library xxx
EBB9935	0	EBBFileF6001createdinlibraryxxx
EBB9936	0	EBBFileF6002createdinlibraryxxx
EBB9937	0	EBBFileF6004createdinlibraryxxx
EBB9938	0	EBBFileF6006createdinlibraryxxx
EBB9939	0	EBBFileF6006convertedfromVersion1xinlibraryxxx
EBB9940	0	EBBFileF6007createdinlibraryxxx
EBB9941	0	EBBFileF6007mergedwitholddatainlibraryxxx
EBB9942	0	EBBFileF6008createdinlibraryxxx
EBB9943	0	EBBFileF6008Icreatedinlibraryxxx
EBB9944	0	EBBFileF6009createdinlibraryxxx
EBB9945	0	EBBFileF6011createdinlibraryxxx
EBB9946	0	EBBFileF6020createdinlibraryxxx
EBB9947	0	EBBFileF6021createdinlibraryxxx
EBB9948	0	EBBFileF6021convertedfromVersionxxxinlibraryxxx
EBB9949	0	EBBOUTQ EBBERRQ created in library xxx
EBB9950	0	EBBOUTQ EBBSTART created in library xxx
EBB9951	0	EBBOUTQ EBBFINAL created in library xxx
EBB9952	0	EBBMSGQ EBBMSGQ created in library xxx

Message ID	Severity	Message Text
EBB9953	0	EBBJOBD EBBJOB created in library xxx
EBB9954	0	This job will delete EBB install libraries. Do you want to proceed? (Y or N)
EBB9988	20	EBB Software Installation DID NOT COMPLETE-call support.
EBB9989	0	EBB Software Installation cancelled by user request



EBB Examples

This appendix provides examples with tasks to compile, collate, and distribute reports. You can use these examples before you begin working with Electronic Burst and Bind. This appendix includes these topics:

- [Section D.1, "Producing a Basic Report Version,"](#)
- [Section D.2, "Producing an Advanced Report Version."](#)

Before You Begin

Choose Generate Demo Spool Files from the Electronic Burst and Bind menu (G98E). The Generate Demo Spool Files program provides three demonstration spool files:

- DEMO_RPT1
- DEMO_RPT2
- DEMO_RPT3

The spool files are in RDY status.

You must move the spool files to the EBBSTART output queue.

D.1 Producing a Basic Report Version

The following example includes tasks you complete to setup a basic EBB version. The example produces a general ledger report, separated by account category and then routes each burst report to a different output queue.

In this example you use DEMO_RPT1. You can change the User Data Spool File Attribute to the name you use for the EBB version ID. In this example, DEMO1 is the attribute name in the spool file, DEMO_RPT1. Since the spool file attribute and name are satisfactory, you do not need to change either.

To produce the Basic Report Version, complete the following tasks:

- To end the EBB monitor
- To add a new version ID
- To add the spool file to the version
- To identify the burst area
- To load select keys
- To create a routing function

- To assign routing functions
- To start the EBB monitor
- To check messages
- To check the output files

To end the EBB monitor

Navigation

From **Electronic Burst and Bind (G98E)**, choose **End EBB Monitor**


Before you create an EBB version, ensure that the EBB monitor is not active.

1. After ending the EBB Monitor, on the **Electronic Burst and Bind** menu (G98E), choose **Display EBB Message Queue**.

The following message displays:

EBB monitor ended

Figure D-1 Display Messages (EBB Monitor Ended) screen



2. Exit (F3) to the **Electronic Burst and Bind** menu.

To add a new version ID


Navigation

From **Electronic Burst and Bind (G98E)**, choose **Maintain EBB Versions**

The EBB Setup File contains the default job and output queues for EBB. The EBB Setup File also stores other default information, such as the monitor delay time and the location of JD Edwards World source. This information displays on the **Maintain EBB Versions** screen. See [Chapter 5, "Overview to Versions"](#) for more information.


1. On **Maintain EBB Versions**, choose **EBB Version - Set Up (F6)**.

Figure D–2 Maintain EBB Versions screen



2. On Add EBB Version ID, enter DEMO1 in the EBB Version ID field.
3. Enter EBB DEMO VERSION in the Version Description field.
4. Complete the following fields and click Enter:
 - `Error Outq
 - `Keep a Spool File
 - `Make a note of the version defaults. You can change them if necessary.

Figure D–3 Add EBB Version ID screen



To add the spool file to the version

After you create a new version ID, the EBB Reports Selection screen should display. If Maintain EBB Version displays, enter 1 in the Option field next to DEMO1.

1. On EBB Reports Selection, choose Display Spool file for selection (F8).

Figure D-4 Spool File Selection (Add) screen



2. On Spool File Selection, enter EBBSTART in the following field:
 - "OUTQ"
3. On Spool File Selection, enter 1 next to DEMO_RPT1 in the Option field.
Notice that 'Selected' displays on the far right next to the file.

Figure D-5 Spool File Selection (DEMO_RPT1) screen

- Exit (F3) to EBB Reports Selection.

The report name DEMO_RPT1 displays in the versions report list.

Figure D-6 EBB Reports Selection (Report Name Displayed) screen

To identify the burst area


After adding the spool file report to the version ID, you should be on the EBB Reports Selection screen. You are now ready to identify the burst area.

You must identify the area on the report (not actual data or data values) for which EBB will burst the report. In this example, you select the Account Category for the burst

area. See [Chapter 13, "Overview to Burst and Bind Criteria"](#) for more information.

1. On EBB Reports Selection, enter 1 in the Option field next to the DEMO_RPT1.


Figure D-7 EBB Reports Selection (Identify Burst Area) screen



2. In the Burst Selection Setup area, enter 2 for Spool file Example.
3. On Spool File Selection, enter EBBSTART in the OUTQ field.
4. Enter 1 next to DEMO_PRT1 in the Option field.

The first page of the report displays.

Figure D-8 Electronic Burst & Bind (Identify Burst Area) screen



5. Move the cursor to the space immediately before the Account Category data area 00002006, and choose Begin Mark (F8).

The system highlights the data 00002006 and the remainder of the report.

6. Move the cursor to the space immediately after 00002006 and choose End Mark (F9).

The system highlights only the data 00002006.

7. Choose Add/Change (F10) to verify the burst area.

On the EBB Row and Column Maintenance window the area you chose on Select Key Maintenance should be in row 006, column 002, and have a length of 008. If your form does not reflect this, choose Delete Requested from the Function menu to clear the burst area. Return to the first page of the report and repeat the previous steps to mark the beginning and end of the burst area.


8. Exit (F3) to the Spool File Selection screen.

To load select keys

After identifying the burst area, you should be on Spool File Selection. You are now ready to load the select keys. This creates select keys for the EBB version. See [Chapter 19, "Load Select Keys"](#) for more information.

1. On Spool File Selection, enter 7 in the Option field next to DEMO_RPT1.

Figure D-9 Spool File Selection (Load Select Keys) screen



2. When the job completes, the following message displays:
Preload Select Keys have completed. You can see New Select Keys in last column.
3. Exit (F3) until you return to the Electronic Burst and Bind menu.

To create a routing function

After loading data in the burst area, you are now ready to create a routing function.

Create a new routing function naming it PRINT2. You will modify the initial PRINT function in this example.

See [Section 22.2, "Creating a Routing Function from an Existing Function"](#) for more information.

Navigation


From Electronic Burst and Bind (G98E), choose Maintain EBB Functions

On Maintain EBB Functions the list of available routing functions displays.


1. On Maintain EBB Functions, enter 1 in the Option field next to the PRINT function.

The PRINT function parameters display on EBB - Maintain Function Description.

Figure D-10 EBB - Maintain Function Description screen




2. Enter PRINT2 in the Function Name field.

Figure D–11 EBB - Maintain Function Description (PRINT 2) screen

3. Exit (F3) to the Maintain EBB Function screen.

Notice that PRINT2 is now in the function list on Maintain EBB Functions.

Figure D–12 Maintain EBB Functions (PRINT 2 Displayed) screen

4. Exit (F3) to the Electronic Burst and Bind menu.

To assign routing functions

You are now ready to determine where to route each select key. You can add routing functions as necessary. See [Chapter 24, "Assign Routing Functions to Select Keys"](#) for more information.


Navigation

From Electronic Burst and Bind (G98E), choose Maintain EBB Versions

1. On Maintain EBB Versions, enter 2 in the Option field next to DEMO1.
Select keys for the report display on the Select Key Maintenance screen.
2. Enter 1 in the Option field for the select key 00002006.
3. On Entity/Function Maintenance, choose Add Function for Entity (F6).
Information for the PRINT function displays on Entity/Function Parm Maintenance.
4. Click Enter.
5. Exit (F3) to Select Key Maintenance.
Notice an * displays next to the 00002006 select key, indicating that a routing function is attached to the select key.
6. On Select Key Maintenance, enter 1 in the Option field next to the 00002006 select key.
7. On Entity/Function Maintenance, choose Add New Function for Entity (F6).
Fields display blank on Entity/Function Parm Maintenance.
8. To display the additional routing functions, choose Retrieve Functions (F4).
9. On Function Selection, enter 4 in the Option field next to the PRINT2 function.
10. On Entity/Function Parm Maintenance, enter EBBFINAL or another output queue in the Parm 1 field to change the output queue.
11. Optionally, enter the number of copies in the Parm 2 field and click Enter.
12. Exit (F3).

The routing functions PRINT and PRINT2 display on Entity/Function Maintenance.

Figure D-13 Entity/Function Maintenance screen



13. Exit (F3) to the Select Key Maintenance screen.

You can assign a new routing function to another select key by choosing another select key and repeating the steps to assigning a routing function.

14. Exit (F3) to the Electronic Burst and Bind menu.

To start the EBB monitor

After assigning routing functions, you are now ready to start the monitor.

Navigation


From Electronic Burst and Bind (G98E), choose Start EBB Monitor

1. After starting the EBB Monitor, on the Electronic Burst and Bind menu (G98E), choose Display EBB Message Queue.

The following message displays:

EBB monitor started

Figure D–14 Display Messages (EBB Monitor Started) screen



2. Exit (F3) to the Electronic Burst and Bind menu.

To check messages

Navigation

From Electronic Burst and Bind (G98E), choose Display EBB Message Queue

Check messages periodically as the monitor processes the report, as well as the active jobs.

The Display Messages screen displays messages if problems arise while the monitor processes the reports. Because EBBSTART is the output queue for one of the burst reports, the monitor attempts to process the report. No EBB version exists for the report, and the monitor generates the following message:

No EBB Version found for spool file with userdata: P98E04

Disregard this message and Exit (F3) the Display Messages screen.

To check the output files

Check the EBBFINAL output queue for the burst, original, and process report, R98E04. View the process report, R98E04, to determine which spool files the monitor creates for the select keys, the spool file IDs, and output queues. The number of reports the monitor creates in the default queue - EBBFINAL, the error queue - EBBERRQ, and other output queues - EBBSTART display on the process report.

Separate reports exist for each select key, as well as the other two select keys for the additional routing functions. Print or view the reports in EBBFINAL and EBBSTART to examine the results of how the system bursts reports and creates banner pages. Also check any reports that might be in EBBERRQ, the error queue.

When the monitor returns to a delay status, EBB has finished processing your jobs and the reports are available in the EBBFINAL out queue. When EBB finishes processing, stop the monitor.

D.2 Producing an Advanced Report Version

The following example explains how to set up an advanced EBB version. In this example, you set up two monthly reports to burst and bind by manager. You will combine the Annual Revenue by Manager Report with the Profit Analysis by Region Report. The second report does not display the manager field. However, because each region reports to a specific manager, you build a cross-reference between the region and the manager codes. EBB then bursts both reports by manager and binds them to route them properly.

In this example you use DEMO_RPT2 and DEMO_RPT3. You must ensure the spool files are in the EBBSTART output queue.

To produce the Advanced Report Version, complete the following tasks:

- To end the EBB monitor
- To add a new version ID
- To add the spool file to the version
- To identify the burst area on DEMO_RPT2
- To identify the burst area on DEMO_RPT3
- To load data in the burst area
- To create a routing function
- To assign routing functions
- To start the EBB monitor
- To check messages
- To check the output files

To end the EBB monitor

Before you create an EBB version, ensure that the EBB monitor is not active.


Navigation**From Electronic Burst and Bind (G98E), choose End EBB Monitor**

1. After ending the EBB Monitor, on the Electronic Burst and Bind menu (G98E), choose Display EBB Message Queue.

The following message displays:

EBB monitor ended

Figure D-15 Display Messages (EBB Monitor Ended) screen



2. Exit (F3) to the Electronic Burst and Bind menu.

To add a new version ID


The EBB Setup File contains the default job and output queues for EBB. The EBB Setup File also stores other default information, such as the monitor delay time and the location of JD Edwards World source. This information displays on the Maintain EBB Versions screen.

Navigation

From Electronic Burst and Bind (G98E), choose Maintain EBB Versions


1. On Maintain EBB Versions, choose EBB Version - Set Up (F6).

Figure D–16 Maintain EBB Versions (Add New Version ID) screen



2. On Add EBB Version ID, enter DEMO2 in the EBB Version ID field.
3. Enter EBB DEMO VERSION 2 in the Version Description field.
4. Complete the following fields and click Enter:
 - `Error Outq
 - `Keep a Spool File

Figure D–17 Add EBB Version ID (DEMO2) screen




To add the spool file to the version

After you create a new version ID, the EBB Reports Selection screen should display. If Maintain EBB Version displays, enter 1 in the Option field next to DEMO2.

1. On EBB Reports Selection, choose Display Spool file for selection (F8).


Figure D–18 EBB Reports Selection (Add Spool File) screen



2. On Spool File Selection, enter EBBSTART in the following field:
3. On Spool File Selection, enter 1 next to DEMO_RPT2 and DEMO_RPT3 in the Option field.

Notice that 'Selected' displays on the far right next to the file.

Figure D–19 Spool File Selection (EBBSTART) screen



4. Exit (F3) to EBB Reports Selection.

The report names DEMO_RPT2 and DEMO_RPT3 display in the versions report list.

To identify the burst area on DEMO_RPT2

After adding the spool file report to the version ID, you should be on the EBB Reports Selection. See [Chapter 13, "Overview to Burst and Bind Criteria"](#) for more information.

1. On EBB Reports Selection, enter a 1 in the Option field for DEMO_RPT2.
2. In the Burst Selection Setup area, enter 2 for the Spool file Example.
3. On Spool File Selection, enter EBBSTART in the OUTQ field.
4. Enter 1 next to DEMO_PRT2 in the Option field.


The first page of the report displays.

5. Move the cursor to the space immediately before the Manager data a).

The system highlights the data JOE and the remainder of the report.

6. Move the cursor to the space immediately after JOE and choose End Mark (F9).

Figure D–20 Electronic Burst & Bind (Identify DEMO_RPT2) screen



7. Choose Add/Change (F10) to verify the burst area.

On the EBB Row and Column Maintenance window the area you chose on Select Key Maintenance should be in row 006, column 002, and have a length of 003. If your form does not reflect this, choose Delete Requested from the Function menu to clear the burst area. Return to the first page of the report and repeat the previous steps to mark the beginning and end of the burst area.

8. Exit (F3) to the EBB Reports Selection screen.

To identify the burst area on DEMO_RPT3

After adding the spool file report to the version ID, you should be on the EBB Reports Selection. See [Chapter 13, "Overview to Burst and Bind Criteria"](#) for more information.

1. On EBB Reports Selection, enter a 1 in the Option field for DEMO_RPT3.
2. In the Burst Selection Setup area, enter 2 for the Spool file Example.
3. On Spool File Selection, enter EBBSTART in the OUTQ field.

4. Enter 1 next to DEMO_RPT3 in the Option field.


The first page of the report displays.

5. Move the cursor to the space immediately before the Region data area C, and choose Begin Mark (F8).

The system highlights the data C and the remainder of the report.

6. Move the cursor to the space immediately after C (to allow for the field to be 3 digits long), and choose End Mark (F9).

Figure D-21 Electronic Burst & Bind (Identify DEMO_RPT3) screen



7. Choose Add/Change (F10) to verify the burst area.

On the EBB Row and Column Maintenance window the area you chose on Select Key Maintenance should be in row 006, column 004, and have a length of 003. If your form does not reflect this, choose Delete Requested from the Function menu to clear the burst area. Return to the first page of the report and repeat the previous steps to mark the beginning and end of the burst area.

8. Exit (F3) until you return to the Maintain EBB Versions screen.

To load data in the burst area

You are now ready to load the data in the burst area for only the DEMO_RPT2. This creates select keys for the EBB version.


You will define a substitute select key for DEMO_RPT3 and therefore, you do not load select keys.

1. On Maintain EBB Versions, enter 5 in the Option field next to DEMO2.

2. On Spool File Selection, enter EBBSTART in the OUTQ.

Both DEMO_RPT2 and DEMO_RPT3 display.

3. Enter 7 in the Option field next to DEMO_RPT2.

Figure D–22 Spool File Selection (Load Data) screen

- When the job completes, the following message displays:
Preload Select Keys have completed. You can see New Select keys in the last column.
- Exit (F3) until you return to the Electronic Burst and Bind menu.

D.2.1 What You Should Know About

Topic	Description
Substitute Select Key Cross-reference in DREAM Writer	The installation package includes the F98E08 file and it contains the cross-reference table DEMO for use in this example. See Chapter 29, "Generate the Cross-Reference Index" for more information.

To define a substitute select key

You use the Manager data area to burst DEMO_RPT2 and DEMO_RPT3. However, Manager is only in the DEMO_RPT2. To burst DEMO_RPT3 on Manager, you must define a substitute select key using Region. You chose Region as the data area in DEMO_RPT3 and it is the original select key in the cross-reference.

Navigation

From Electronic Burst and Bind (G98E), choose Maintain EBB Versions

- On Maintain EBB Versions, enter 1 in the Option field next to the DEMO2 version.
- On EBB Reports Selection, enter 2 in the Option field for DEMO-RPT3.
- On Substitute Key Maintenance, enter N in the Rebuild Cross-Reference field.
- Enter DEMO in the Table Number field.
- Enter N in the Print Substitute Select Key field and click Enter.

Figure D–23 Substitute Key Maintenance screen

EBB Reports Selection displays.

6. Exit (F3) until you return to Maintain EBB Versions.
7. On Maintain EBB Versions, enter 1 in the Option field for DEMO2.

On EBB Reports Selection, the notation SK indicates that a substitute select key exists for this report.

Figure D–24 EBB Reports Selection (Notation SK) screen

P	Seq	Num	TY	Form/Group	Name/Vers	Description
	001	S	DEMO_RPT1	EBB_RPT1	SPOOL	
	002	S	DEMO_RPT2	EBB_RPT2	SPOOL	SK
	003	S	DEMO_RPT3	EBB_RPT3	SPOOL	

8. Exit (F3) until you return to the Electronic Burst and Bind menu.

To create a routing function


Create a new routing function, XXXX, for this example. Available routing functions display on Maintain EBB Functions.

Navigation

From Electronic Burst and Bind (G98E), choose Maintain EBB Functions


1. On Maintain EBB Functions, choose Create Function (F6).

Figure D-25 Maintain EBB Functions (Create Function) screen



The fields display blank on EBB Maintain Function Description.

Figure D-26 EBB - Maintain Function Description (Blank) screen




2. Complete the following fields:
 - `Description

- Parameters
3. Enter the following in the Command String field:
chgsplfa file (&) job(&/&/&) splnbr(&) formtype(XXX)
 4. Enter the following in the Default Parm 1 through 5 fields respectively:
 - *SPLNAM
 - *JOBJUM
 - *USER
 - *JOBNAM
 - XXXX (where XXXX is the form type name)

Figure D-27 EBB - Maintain Function Description (Default Parameters) screen

5. Click Add.
6. Exit (F3) to Maintain EBB Functions.
Notice that XXXX is now in the function list.

Figure D-28 Maintain EBB Functions (XXXX) screen



7. Exit (F3) until you return to the Electronic Burst and Bind menu.

To assign routing functions


You now determine where to route each select key.

Navigation


From Electronic Burst and Bind (G98E), choose **Maintain EBB Versions**

1. On Maintain EBB Versions, enter 2 in the Option field next to DEMO2.
Select keys for the report display on the Select Key Maintenance screen.


Figure D-29 Select Key Maintenance (Assign Routing) screen



2. Enter 1 in the Option field for the Ann select key.

Figure D–30 Entity/Function Maintenance (Ann) screen


3. On Entity/Function Maintenance, choose Add New Function for Entity (F6). Information for the PRINT function displays on Entity/Function Params Maintenance.

Figure D–31 Entity/Maintenance Parameters Maintenance (Add New) screen

4. Click Enter.
5. Exit (F3) to Select Key Maintenance.


An * displays next to the Ann select key, indicating that a routing function is attached to the select key.

Figure D–32 Select Key Maintenance (* Displayed) screen



6. On Select Key Maintenance, enter 1 next to the Ann select key.
7. On Entity/Function Maintenance, choose Add New Function for Entity (F6).
Fields display blank on Entity/Function Params Maintenance.
8. To display the additional routing functions, choose Retrieve Functions (F4).

Figure D–33 Function Selection (Retrieve Functions) screen



9. On Function Selection, enter 4 in the Option field next to the XXXX function.

Figure D–34 Entity/Function Parameters Maintenance (XXXX Function) screen

10. On Entity/Function Params Maintenance, click Enter.

11. Exit (F3).


The routing functions PRINT and XXX display on Entity/Function Maintenance.

Figure D–35 Entity/Function Maintenance (PRINT and XXX Displayed) screen

Function	Seq#	Parm 1	Parm 2	Parm 3	Parm 4	Parm 5
PRINT	001	EBBFJNRL	5	100		
XXXX	002	*SPLNAM	*JOBJUR	*USER	*JOBNAM	XXXX

12. Exit (F3) to Select Key Maintenance.

Figure D-36 Select Key Maintenance (Exit) screen



13. Exit (F3) to the Electronic Burst and Bind menu.

To start the EBB monitor

After assigning routing functions, you are now ready to start the monitor.

Navigation


From Electronic Burst and Bind (G98E), choose Start EBB Monitor

1. After starting the EBB Monitor, on the Electronic Burst and Bind menu (G98E), choose Display EBB Message Queue.

The following message displays:

EBB monitor started

Figure D-37 Display Messages (EBB Monitor Started) screen



2. Exit (F3) to the Electronic Burst and Bind menu.

To check messages

Navigation

From Electronic Burst and Bind (G98E), choose Display EBB Message Queue

Check messages periodically as the monitor processes the report, as well as the active jobs. The Display Messages screen displays messages if problems arise while the monitor processes the reports. Because EBBSTART is the output queue for one of the burst reports, the monitor attempts to process the report. No EBB version exists for the report, and the monitor generates the following message:

No EBB Version found for spool file with userdata: P98E04

Disregard this message and Exit (F3) the Display Messages screen.

To check the output files

Check the EBBFINAL output queue for the burst, original, and process report, R98E04. View the process report, R98E04, to see which spool files the monitor creates for the select keys, the spool file IDs, and output queues. The number of reports the monitor creates in the default queue - EBBFINAL, the error queue - EBBERRQ, and other output queues - EBBSTART display on the process report.

Separate reports exist for each select key, as well as the other two select keys for the additional routing functions. Print or view the reports in EBBFINAL and EBBSTART to see how the system bursts reports and creates banner pages. Also check any reports that might be in EBBERRQ the error queue.

When the monitor returns to a delay status, EBB has finished processing your jobs and the reports are available in the EBBFINAL out queue. When EBB finishes processing, stop the monitor.

A

About burst and bind criteria, 13-1
About EBB reports selection, 9-1
About EBB setup and environment, 2-1
About EBB versions, 5-1
About routing functions, 21-1
About select keys, 18-1
About substitute select keys, 27-1
About the Monitor, 31-1
Accessing EBB reports selection, 10-1
Adding
 an EBB version, 6-1
Adding a DREAM Writer report version for P98E08, 30-1
Adding a report to a version, 11-1
Adding an EBB version, 6-1
Adding select keys, 20-1
Assigning a routing function to a single select key, 24-4
Assigning a routing function to multiple select keys, 24-8
Assigning routing functions to select keys, 24-1
Assigning sequence numbers to select keys, 30-6
Assigning the PRINT routing function, 24-1

B

Banner page
 define for print function, 25-1
 to override, 7-3
Basic processes of EBB, 1-1
Bind criteria
 defined, 13-1
Binding
 defined, 1-3
 example, 1-3
Burst and bind criteria
 defined, 13-1
Burst area
 setting up FASTR and World Writer reports, 15-4
 setting up using DDS, 14-1
 setting up using spooled file, 15-1
Burst criteria
 defined, 13-1
Bursting

defined, 1-2
example, 1-2

C

Changing parameters for a select key, 25-1
Changing the defaults, 7-3
Clearing the EBB history log, 36-1
Command line string requirements, 21-2
Creating a new routing function, 22-3
Creating a new version using a model, 8-1
Creating a routing function from another function, 22-2
Cross reference table
 updating, 30-1
Customizing the EBB processing environment, 4-1

D

Data description specification
 use in EBB, 14-1
DDS
 use in EBB, 14-1
DDS considerations, 14-1
Defaults
 changing an EBB version, 7-3
Defining substitute select keys, 28-1
Defining version parameters, 30-4
Deleting a routing function in EBB, 23-1
Deleting a version, 7-2
Demo routing functions, 21-1
Displaying the EBB message queue, 35-1
DREAM Writer
 P98E08, 30-1

E

EBB Monitor
 setup file, 31-1
EBB monitor
 defined, 31-1
 ending, 34-1
 requirements to start, 31-1
 restarting, 34-1
 starting, 33-1
EBB setup files

- updating, 3-1
- EBB Versions
 - deleting, 7-2
- EBB versions
 - changing defaults, 7-3
 - maintaining, 7-1
- EBBSTART
 - moving spooled files, 31-1
- Ending the monitor, 34-1
- Entity/functions report
 - printing, 26-1
- Entity/routing ID
 - change, 25-1

F

Forms

- Additional Parameters, 30-4
- Burst Selection Setup, 19-1
- Data Sequence Setup, 30-6
- DREAM Writer Version Copy, 30-1
- EBB Reports Selection, 14-1, 19-1, 28-1
- EBB Select Key Maintenance, 20-1
- Maintain EBB Versions, 19-1, 28-1, 31-1
- Processing Options Revisions, 30-5
- Select Key Maintenance, 20-1
- Spool File Selection, 19-1, 31-1
- Substitute Key Maintenance, 28-1
- Versions List, 30-1

G

- Generating the cross-reference index, 29-1

H

- History log
 - defined, 36-1
 - viewing
 - clearing, 36-1

J

- JOBQ
 - add to subsystem, 4-1

K

- Keywords
 - reserved, 21-2

L

- Loading select keys, 19-1
- Loading select keys for multiple spool files, 19-2

M

- Maintaining EBB versions, 7-1
- Message queue
 - displaying, 35-1

- Model version
 - creating, 8-1
 - defined, 8-1
 - setting up, 8-1
- Moving spool files to EBBSTART, 31-1

P

- PRINT routing function, 21-2
 - required, 21-2
- Printing a version information report, 17-1
- Printing the entity/functions report, 26-1
- Process flow
 - example, 1-4
- Process report
 - defined, 37-1
 - viewing, 37-1
- Processing environment
 - customize, 4-1
- Processing option revisions
 - substitute select keys, 30-5
- Programs and IDs
 - P6009 (version output parameters), 7-3
 - P6010 (maintain EBB versions), 6-1, 7-1, 19-1
 - P6012 (EBB reports selection), 10-1, 14-1, 15-1, 19-1
 - P6014A (select key maintenance), 15-1
 - P6015 (spool file selection), 15-1, 19-1
 - P6015D (spool file selection), 11-1
 - P6020 (select key maintenance), 20-1, 24-1, 24-8
 - P6020B (EBB select key maintenance), 20-1
 - P6021 (entity/function maintenance), 24-1
 - P6021A (entity/function maintenance
 - global), 24-8
 - P6024 (EBB - maintain function description), 22-2
 - P6025 (maintain EBB functions), 22-2
 - P6027 (entity/function parameters
 - maintenance), 24-1
 - P6027A (entity/parameters maintenance), 24-8
 - P6033 (function selection), 24-4, 24-8
 - P6099 (EBB setup file maintenance), 3-1
 - P98300 (versions list), 30-1
 - P98301 (version identification), 30-1
 - P983011 (additional parameters), 30-4
 - P98303 (data sequence setup), 30-6
 - P98312 (processing options revisions), 30-5
 - P98CPYW (DREAM Writer version copy), 30-1
 - P98E (EBB reinstall data files), 3-1

R

- Report
 - adding to version, 11-1
- Reports
 - sequencing, 12-1
- Routing
 - defined, 1-4
 - example, 1-4
- Routing functions
 - assigning PRINT, 24-1

- assigning to multiple select keys, 24-8
- assigning to single select key, 24-4
- command line string requirements, 21-2
- creating a new, 22-3
- creating from existing function, 22-2
- customize parameters, 25-1
- defined, 21-1
- deleting, 23-1
- keywords, 21-2

- deleting, 7-2
- information report, 17-1
- Viewing the EBB process report, 37-1

S

Screens

- Add EBB Version, 6-1
- EBB - Maintain Function Description, 22-2
- EBB Reinstall Data Files, 3-1
- EBB Reports Selection, 10-1, 15-1
- EBB Setup File Maintenance, 3-1
- Entity/Function Maintenance, 24-1, 24-8, 25-1
- Entity/Function Parameters Maintenance, 24-1, 25-1
- Entity/Parameters Maintenance, 24-8
- Function Selection, 24-4, 24-8
- Maintain EBB Function, 22-2
- Maintain EBB Versions, 6-1, 7-1, 25-1
- Select Key Maintenance, 15-1, 24-1, 24-8, 25-1
- Spool File Selection, 11-1, 15-1
- Version Output Parameters, 7-3

Select keys

- adding
 - maintaining, 20-1
- defined, 18-1
- loading, 19-1

Selecting Data, 30-5

Sequencing

- reports, 12-1
- substitute select keys, 30-6

Sequencing reports, 12-1

Setting up a model version, 8-1

Setting up burst areas using DDS, 14-1

Setting up burst areas using spool files, 15-1

Setting up FASTR and World Writer report for burst criteria, 15-4

Starting the monitor, 33-1

Substitute select key

- cross reference table, 27-1
- defined, 27-1
- defining, 28-1
- example, 27-1
- updating cross reference, 30-1

U

Updating EBB setup files, 3-1

Updating the cross-reference table, 30-1

Using a model version, 8-1

V

Version

- defined, 5-1

