# **Oracle® Enterprise Manager Ops Center**

Provisioning Oracle Solaris 10 Operating Systems

12c Release 3 (12.3.0.0.0)

#### E60024-01

June 2015

This document provides an end-to-end example for how to use Oracle Enterprise Manager Ops Center to create and apply an OS Provisioning deployment plan to install an Oracle Solaris 10 operating system on a configured SPARC system.

## Introduction

Oracle Enterprise Manager Ops Center streamlines the process of installing an Oracle Solaris 10 operating system (OS) on configured or unconfigured hardware.

Oracle Enterprise Manager Ops Center uses an OS image that is stored in a software update library to provision the target servers. The library is located either in a directory on the Enterprise Controller or on a Network Attached Storage (NAS) appliance that the Enterprise Controller can access.

As shown in Figure 1, when you use Ops Center to provision, you create two profiles to define the provisioning parameters and a plan to apply your configuration selection to target systems. Several different deployment plans are available for OS provisioning. Some are complex or multi-step plans where OS provisioning is part of a larger process, such as installing and configuring a server. The Provision OS deployment plan just provisions the operating system.

### Figure 1 OS Provisioning Flow



As shown in Figure 1, the following is an overview of the OS provisioning process:

- 1. Create an OS Provisioning profile: Defines the OS provisioning parameters, including the platform-specific OS image and software package, file system layout, user accounts, naming services, and other installation requirements.
- 2. Create an OS Configuration profile: Defines the configuration parameters, including the platform, how the OS is managed (with or without an agent), MPxIO and networking options.
- **3. Create an OS Provisioning Deployment Plan**: Defines the profiles to use for the provisioning job. To successfully create the plan, the OS Provisioning and OS Configuration profiles must be the same sub-type. For example, Solaris SPARC.
- **4. Apply the OS Provisioning Deployment Plan to selected targets**: Defines the targets to provision, defines the boot interface resource assignments, network

# ORACLE

resource assignments, and server pool assignment (if applicable), and schedule when to begin the provisioning job.

You can reuse the OS Provisioning and OS Configuration profiles and the deployment plan to provision other systems or groups of systems.

**Note:** To provision operating systems on logical domains, you must use the OS Provisioning and OS Configuration profiles that have Logical Domains as a subtype. The profiles described in this document provision an operating system on configured systems.

See Planning for Operating System Provisioning in the *Oracle Enterprise Manager Ops Center Operate Reference* for things to consider before provisioning.

When you install the Oracle Enterprise Manager Ops Center software, you have the option to create a Linux, Oracle Solaris 8-10 Software Update Library. The library contains the OS images needed for provisioning, upgrading, and updating (patching) an Oracle Solaris 10 operating system.

Profiles and plans simplify and standardize the procedures between different operating systems and platforms. The profiles take care of many of the configuration requirements for you and the plan defines the systems to provision.

Beginning with Oracle Enterprise Manager Ops Center Release 2 (12.2.0.0.0), you must use two profiles to define your OS provisioning job:

- **1. OS Provisioning profile**: Defines the image, provisioning, and installation requirements.
- **2. OS Configuration profile**: Defines the OS and network configuration for a specific image.

You can reuse any of the profiles and plans to quickly provision other systems when new hardware is acquired or provision existing hardware. You can install the OS on a bare metal system or on a configured system. This example shows how to create and use an OS Provisioning profile, OS Configuration profile, and Provision OS plan in Oracle Enterprise Manager Ops Center to install an Oracle Solaris 10 operating system on a configured SPARC server.

This document provides a brief overview of the components used in provisioning a configured system with Oracle Solaris 10 and an end-to-end example. The example does not use the Solaris JumpStart Enterprise Toolkit (JET). If you do use JET, the Enterprise Controller and Proxy Controller must be installed on Oracle Solaris.

See Related Articles and Resources for links to related information and articles, including links to more information on JET.

## What You Will Need

You will need the following to provision an Oracle Solaris 10 operating system:

- An Oracle Solaris 10 OS image, imported into the Initial EC software library.
- A Proxy Controller located on the same subnet as the target hosts with DHCP services configured for SPARC system.
- A discovered service processor that is the target for the provisioning job.

- The roles and permissions to complete the tasks. You need the following Oracle Enterprise Manager Ops Center roles:
  - **Update Admin** or **Plan/Profile Admin** to create an OS Provisioning profile, OS Configuration profile, and Provision OS deployment plan.
  - **Update Admin** to apply the plan.

## Provisioning an Oracle Solaris 10 Operating System

You can create OS profiles for provisioning Solaris OS on SPARC and x86 systems. Complete the following actions to provision Oracle Solaris 10 operating system.

- Create an OS Provisioning Profile for Oracle Solaris 10 Operating System
- Create an OS Configuration Profile for an Oracle Solaris 10 Operating System
- Create a Provision OS Deployment Plan for Oracle Solaris 10 Operating System
- Apply the Provision OS Deployment Plan

### Create an OS Provisioning Profile for Oracle Solaris 10 Operating System

Complete the following steps to create an OS Provisioning profile:

- 1. Expand Plan Management in the Navigation pane.
- 2. Select OS Provisioning under the Profiles and Policies section.

Mavigation
> Message Center
> Assets
🖂 Plan Management
\$
🗄 🗾 Update Storage Appliances
🖃 🦉 Profiles and Policies
🕀 🎬 Discovery
🕀 🧱 Service Processor
🕀 💹 RAID Controller
🕀 🦉 Firmware
🕀 🦉 Dynamic System Domain
🗄 🧾 OS Provisioning 🔒
🕀 🧾 Logical Domain 🖤

**3.** Click **Create Profile** in the Actions pane.

» Actions	
🖂 Organize	
🛃 Create Profile	

- **4.** Define the following profile parameters in the **Create Profile-OS Provisioning** wizard, then click **Next**.
  - Name: The name of the profile.
  - Description: A description of the profile.
  - Subtype: Select Solaris SPARC.
  - Target Type: The target type is automatically defined to SPARC type.

Identify Profile	
* Name:	S10_Update 10 SPARC OSP
Description:	Solaris 10 Update 10 SPARC, entire distribution including OEM support
* Subtype:	Subtype
	Oracle VM Server for SPARC
	Logical Domain
	Orade Linux
	Oracle VM Server for x86
	Red Hat Linux
	SUSE Linux
	JET Template
	Solaris SPARC
	Solaris x86
Target Type:	Target Type
	OSP SPARC

5. Select an OS Image, OS Image Version, and Software Group. This example does not include custom scripts. Click Next.

Specify OSP Parameters					
Select an OS image from the list of images available. Select the software group that this OS profile installs.					
* OS Image:SUNWCAT_Solaris_10_Sparc_U10_Official_D\ 💙					
* Software Group:	Entire Distribution plus OEM support				
	Entire Distribution				
	Developer System Support				
	End User System Support				
	Core System Support				
	Reduced Networking Core System Support				
	Include Custom Scripts				

- 6. Specify the following OS setup parameters:
  - Language: Select a language for the OS.
  - Time Zone: Specify the time zone for the OS.
  - Terminal Type: Enter a terminal type, if other than the default type listed.
  - Console Serial Port: A default port appears in the wizard. If incorrect, select the correct console serial port device for your environment. This port enables you to monitor the installation using a serial connection.
  - Console Baud Rate: A default serial port device baud rate is provided. If incorrect, select the correct baud rate for your device.

- NFS4 Domain: Enter the NFS4 domain name that the target system will use. The dynamic value for NFSv4 domain name enables the NFSv4 domain to be derived dynamically, at run time, based on the naming service configuration. You can also provide valid domain name to hard code the value for NFSv4 domain.
- Password: Enter the root password for the root user on systems provisioned using this profile. Re-enter the password for confirmation. The password used in this example is admin.

Specify OS Setup		* Indicates Required Field
Specify language, time zor	ne, terminal type, console and root password for	the OS.
Language:	U.S.A. (en_US.ISO8859-15)	~
Time Zone:	GMT	<b>*</b>
Terminal Type:		
Console Serial Port:	ttya 💌	
Console Baud Rate:	9600	
NFS4 Domain:	dynamic	
* Root Password:	•••••	
* Confirm Password:	•••••	
	Manual Net Boot	

- **7.** Click **Next** to skip specifying the Installation Parameters. To learn more about using the JumpStart Enterprise Toolkit (JET), see the JumpStart Enterprise Toolkit appendix in the *Oracle Enterprise Manager Ops Center Operate Reference*.
- 8. Review and edit the default file system layout, then click Next.

This example uses the default layout. To specify changes, click the size field for the file system and redefine the size. To add another file system, click the **Add** icon and complete the fields.

File Systems (2	)		
File System Type	Mount Point	Device	Size (MB)
swap	swap	rootdisk.s1	4096
ufs	1	rootdisk.s0	Remaining unused space

9. Select None, then click Next to skip using a naming service.

Specify Nami	ng Servi	es			* Indicates Required Field
Specify the name : If the name servic Otherwise, the ho	service, the e is specified stname will b	domain nan I, the hostn e generate	ne, and th ame woul d by subs	e correspor d be autom tituting the	nding name server. latically derived from it. • '.' in the target's IP address with '-'.
Name Service:	⊙ NONE	🚫 DNS	🚫 NIS	🚫 NIS+	◯ LDAP

**10.** Review the parameters selected for Oracle Solaris 10 operating system provisioning, then click **Finish** to save the profile.

ımmary				
view the properties of the	profile. Click Fir	nish to save the pr	ofile.	
Nan	ne: S10_Upda	te 10 SPARC OSP		
Description	on: Solaris 10	Update 10 SPARC	entire distribution including OEM support	
Target Ty	pe: OSP SPAR	C		
OS Ima	ge: _SUNWCA	T_Solaris_10_Spa	rc_U10_Official_DVD (ISO)	
Software Gro	up: Entire Dist	ribution plus OEM s	upport	
Langua	ge: U.S.A. (en	_US.IS08859-15)		
Time Zo	ne: GMT			
Terminal Ty	pe:			E
Console Serial Po	ort: ttya			
Console Baud Ra	ate: 9600			
NFS4 Doma	ain: dynamic			
Manual Net Bo	oot:			
JET Module	es:			
File Systems (2)				
File System Type	Mount Point	Device	Size (MB)	
swap	swap	rootdisk.s1	4096	

The profile appears in the center pane and in the **Profiles and Policies** section of **Plan Management** in the left Navigation pane.

S10_Update 1	LO SPAR	RC OSP				📡 🛱
Details Ref	ferrers	Version History				
Name: Description: Target Type:	S10_Upd Solaris 1 including OSP SPA	late 10 SPARC OSP 0 Update 10 SPARC, entire OEM support .RC	distribution	Subtype: Version Last Modified	: Solaris SPARC : 1 : 02/10/2014 8:26:23 am N	IST
Profile Details						
OS In Time Z	nage:( Zone: @	SUNWCAT_Solaris_10_Sp ISO) BMT	arc_U10_Of	ficial_DVD	Language: Terminal Type:	U.S.A. (en_US.IS08859-15)
Console Serial	Port: tt	iya			Console Baud Rate:	9600
[	Manua Save	al Net Boot NVRAMRC values				
:	Software	e Group: Entire Distribution	on plus OEM	support	Name Service: NONE	
File Systems (	(2)					
File System Type	e	Mount Point	Device	Siz	e (MB)	
swap		swap	rootdisk.s1	40	96	
ufs		1	rootdisk.s0	Re	maining unused space	

# Create an OS Configuration Profile for an Oracle Solaris 10 Operating System

The OS Configuration profile defines how the OS is managed (with or without an agent) and the networking options. The configuration profile is platform-specific.

The OS Configuration profile lets you define the network interface that you want to use on the operating system. The first interface you define in this wizard is the boot interface and also the primary interface. You can add more than one network interface. When you apply the plan to a target, you can select which network interface is the primary interface and define the IP address. **Note:** Before you begin, contact your network administrator for the list of available networks and interfaces.

The wizard lets you choose from a list of 32 possible interfaces. Your network administrator can tell you which of the possible interfaces are available.

Complete the following steps to create a profile for configuring an Oracle Solaris 10 operating system:

- **1.** Expand **Plan Management** in the Navigation pane, scroll down to **Profiles and Policies**.
- **2.** Select **OS Configuration** in the **Profiles and Policies** tree. A list of existing OS configuration profiles appears.
- 3. Click Create Profile in the Actions pane.
- **4.** Define the following profile parameters, then click **Next**.
  - Name: The name of the profile.
  - Description: A description for the profile.
  - Subtype: Select **Solaris**.
  - Target Type: Select **SPARC**.

Identify Profile		* Indicates Required Field
* Name:	Oracle Solaris 10 Configuring Profile	
Description:	Oracle Solaris 10 Configuring Profile	
* Subtype:	Subtype	
	Oracle VM Server for SPARC	
	Oracle Linux	
	Oracle VM Server for x86	
	Red Hat Linux	
	SUSE Linux	
	Solaris	
	JET Template	
Target Type:	Target Type	
	OSP SPARC	
	OSP x86	

**5.** Select **Automatically Manage with Oracle Enterprise Manager Ops Center** and **Deploy the Agent Controller.** These options provide the most robust management and monitoring capabilities. Select **Enable Multiplexed I/O (MPxIO)** to enable SAN storage connectivity. When you enable MPxIO on the global zone, you are able to associate a SAN storage device to the global zone and use the storage for zones. Click **Next**.



6. Select None for the Networking Services, then click Next.

Specify Networking
Specify if the OS would need to use IPMP groups or IEEE 802.3ad Link Aggregations.
O Use Link Aggregation
O Use IPMP
<ul> <li>None</li> </ul>

**7.** Select a network interface that you want to use in the configuring process, then click **Next**. This example uses net\_0 for the network interface, which is also the default boot interface. The address allocation method is static IP address allocation. You define the IP address when you apply the deployment plan to the target.

**Note:** By default, the primary interface is the boot interface. You can change the primary interface to a different interface when you deploy the plan.

pecify Netw	ork Interfaces	nt to use on the OS.	
Network Inter	faces (1)		
Controller	Interface	Address Allocation Method	
default	net_0	Use Static IP	

**8.** Review the Summary of the parameters selected for configuring Oracle Solaris 10 operating system. Click **Finish** to create the configuration profile.

Summary			
Review the properties of the pro	file. Click Finis	h to save the profile.	
Name:	S10 SPARC OS Configuration		
Description:	Oracle Solaris 10 SPARC		
Target Type:	OSP SPARC		
Automatically Manage with Oracle Enterprise Manager Ops Center:	✓		
Deploy Agent Controller:	1		
Enable Multiplexed I/O (MPxIO):			
Network Interfaces (1)			
Controller Interfa	ice	Address Allocation Method	
default net_0	)	Use Static IP	

The profile appears in the center pane and in the **Profiles and Policies** section of **Plan Management** in the left Navigation pane.

🖉 S10 SPARC OS 🛛	Configuration			
Details Refer	rrers Ver	sion History		
Name: S1 Description: Or	10 SPARC OS Cor racle Solaris 10 Si	figuration PARC	Sub Ver	otype: Solaris rsion: 1
Profile Details	SF SFARU		Last Mou	aneu: 02/10/2014 5.05.51 amm51
<ul> <li>✓</li> </ul>	Automatically Ma Enterprise Mana Enable Multiplexe	nage with Oracle ger Ops Center ed VO (MPxIO)		Deploy Agent Controller
Network Interfa	aces (1)			
Controller		Interface	Add	ddress Allocation Method
default		net_0	Use	se Static IP

# Create a Provision OS Deployment Plan for Oracle Solaris 10 Operating System

When you create the plan, both the OS Provisioning profile and the OS Configuration profile must have the same platform subtype, either SPARC or x86. This example uses the Solaris SPARC subtype for both profiles.

Perform the following steps to create a deployment plan for provisioning Oracle Solaris 10 operating system:

- **1.** Expand **Plan Management** in the Navigation pane, then select **Provision OS** in the Deployment Plans section.
- **2.** Click **Create Plan from Template** from the Actions pane.
- **3.** Enter the following parameters, then click **Save** to create a deployment plan.
  - Name: The name of the deployment plan.
  - Description: A description of the deployment plan.

- Failure Policy: Complete as much as possible.
- Deployment Plan Steps: For each step, click the Associated Profile/Deployment Plan field to display a list of available profiles. Select the OS Provisioning profile and OS Configuration profile that you created earlier.

Create a	Deployment Plan (?	
----------	--------------------	--

* Plan Name: S10	U10 SPARC	
Description: Use distr	this plan to provision Orade Solaris 10, upd ibution, including <u>QEM</u> . SPARC	jate 10, full
Failure Policy: 🖲 S	stop at failure 🔍 Complete as much a	is possible
Target Type: Serve	rs sion OS	
Deployment Plan Ste	ps IT	
Step	Profile/Plan Type	Associated Profile/Deployment Plan
Step Provision OS (Required	Profile/Plan Type step) OS Provisioning Profile	Associated Profile/Deployment Plan S10_Update 10 SPARC OSP v1 (Solaris SPARC

Expand **Plan Management**, then expand **Provision OS**. Select the deployment plan to view its details in the center pane.

🗾 S10 U10 SP	ARC			
Details R	esults Referrers Version His	story Jobs		
Plan Name:	S10 U10 SPARC	Created:	02/10/2014 9:29:58 a	m MST
Version:	1	Last Modified:	02/10/2014 9:29:58 a	m MST
Description:	Use this plan to provision Oracle Solaris 10,	Template:	Provision OS v3	
	update 10, full distribution, including OEM. SPARC	Referrers:	0	
Target Type:	OSP SPARC			
Failure Policy:	Stop at failure			
Deployment P	lan Steps			
Step	Associated Profile/Deployment Plan		Number of Results	Assigne
Provision OS	S10_Update 10 SPARC OSP v1		0	0
Configure OS	S10 SPARC OS Configuration v1		1	-

## Apply the Provision OS Deployment Plan

Perform the following steps to apply the deployment plan and provision a system:

- **1.** Expand **Plan Management**, then expand **Deployment Plans** and select the plan. The plan details appear in the center pane.
- 2. Click Apply Deployment Plan in the Actions pane.

🕑 Deploy
🧭 Apply Deployment Plan

**3.** Expand Servers in the target selector. Select the target assets and click **Add to Target List**. The default setting filters the assets according to the plan's characteristics. You can only select eligible systems to add to the Target List. Select **Apply minimal interaction** to limit or eliminate the need for you to provide input during the provisioning job. Click **Next** to open the deployment plan.

Available Items			Target List(1)
Assets	Product Name	Description	Assets 🔺
🚊 🚂 All Assets		SystemGroup	Myhost_1
🛓 🛲 Servers		ServerPseudoPagir	
Myhost_1	SPARC T-4	Server	
🗐 📾 Myhost 2	Sun Fire X4100	Server	
Mvhost 2	Oracle Solaris 11.	GlobalZone	
😑 🛲 Mvhost sp 3	Sun Fire T2000 S.	Server	
Mvhost 3	C-1	CI-L-17 >	
		Add to Target List	Persoue from Terrat List

- **4.** On the Introduction page for the deployment plan, the check box is selected to skip steps that are not included in the plan. Click **Next**.
- 5. Click Next to skip the OS Provision introduction page.
- 6. On the Boot Interface Resource Assignments page, verify that the Network and Interface are what you want to use. Complete the last octet of the IP address, or enter a different IP address. Optionally, you can provide a host name. Click Next.
- 7. Review the Provision OS Summary page, then click Next.
- **8.** Click **Next** to skip the Configure OS introduction page.
- **9.** Review the network resource assignment. You can edit the fields, if needed. Click **Next**.

**Note:** Verify with your administrator that the network interface, such as net\_30, is available. The list is possible interfaces, the available interfaces is not known.

- **10.** Select **Do not assign to a Server Pool**. The new server will execute in standalone mode. You can add the server to a pool at a later time. Click **Next**.
- **11.** Review the Configure OS Summary page, then click **Next**.
- **12.** Select **Now** to schedule the job for now. Click **Apply** to apply the deployment plan.

The provisioning job takes time to complete. You can view the progress and status of the provisioning job from the Jobs pane.

When the job is completed, go to **Assets** and expand **Servers** to see your operating system. Click the operating system in the Navigation pane to display the details in the center pane.

# What's Next?

You can use the OS Provisioning and OS Configuration profiles to consistently and quickly provision and update your Oracle Solaris 10 operating system. You can use the profiles and plans to define which components must be installed and the level of automation during the installation. You can identify dependencies, download update packages or updates from the appropriate vendor sites, maintain consistent component configuration of your systems to the latest security updates.

Depending on the plan, you can either use the OS Provisioning and OS Configuration profiles or the Provision OS deployment plan as steps in the following plans:

- Install Server: This multi-step plan contains steps that use profiles to deploy a server. With this plan you can provision the OS, update the BIOS, update the OS, install software, execute preinstall and postinstall scripts, add operational profiles, add monitoring profiles, and create guests.
- Configure and Install Dynamic System Domain: This multi-step plan contains steps that use a profile to create a Dynamic System Domain and the Install Server plan to install and update the OS.
- Configure M-Series Hardware, Create and Install Domain: This complex plan contains steps that use profiles to configure a service processor, update firmware, and create a Dynamic System Domain. You can add a step to use the Install Server plan to install and update the OS on an M-series system.
- Configure Server Hardware and Install OS: This complex plan contains steps that use profiles to configure the service processor, configure the RAID Controller, and update firmware. You can add a step to use the Install Server plan to install and update the OS.

When you create a multi-step or complex plan from the template, you often have the choice to add or skip steps. You can choose to skip steps, such as updating the BIOS.

Once provisioned, you can associate a storage library with the global zone, deploy zones on the operating system, or monitor and manage the system. Go to <a href="http://docs.oracle.com/cd/E40871\_01/nav/operatehowto.htm">http://docs.oracle.com/cd/E40871\_01/nav/operatehowto.htm</a> for information about how to use Oracle Enterprise Manager Ops Center to help you operate your environment.

## **Related Articles and Resources**

For more information, see the Oracle Enterprise Manager Ops Center Documentation Library at http://docs.oracle.com/cd/E59957\_01/index.htm.

The following chapters in the *Oracle Enterprise Manager Configure Reference* and *Oracle Enterprise Manager Operate Reference* contain more information:

- See Asset Management for more information on discovery, declaring servers, and an example discovery file.
- See Hardware Management for how to create SSH and IPMI credentials.
- See OS Provisioning for more information about OS provisioning, Enterprise Controller and Proxy Controller requirements, and JET.

To learn more about using JET, see the JumpStart Enterprise Toolkit appendix in the Oracle Enterprise Manager Ops Center Operate Reference.

The Oracle Enterprise Manager Ops Center Administration Guide has information about user roles and permissions. To configure the DHCP services for OS

provisioning, see Configuring DHCP and Subnets for OS Provisioning in Oracle Enterprise Manager Ops Center Administration Guide.

For end-to-end examples, see the workflows and how to documentation in the library. For deployment tasks, go to http://docs.oracle.com/cd/E59957\_01/nav/deploy.htm and for operate tasks go to http://docs.oracle.com/cd/E59957\_ 01/nav/deploy.htm 01/nav/operate.htm.

## **Documentation Accessibility**

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc.

#### Access to Oracle Support

Oracle customers that have purchased support have access to electronic support through My Oracle Support. For information, visit

http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info or visit
http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs if you are hearing
impaired.

Oracle Enterprise Manager Ops Center Provisioning Oracle Solaris 10 Operating Systems, 12c Release 3 (12.3.0.0.0) E60024-01

Copyright  $\ensuremath{\textcircled{O}}$  2007, 2015, Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.