

Oracle® Traffic Director

Command-Line Reference

11g Release 1 (11.1.1.7)

E21037-03

March 2013

Oracle Traffic Director Command-Line Reference, 11g Release 1 (11.1.1.7)

E21037-03

Copyright © 2011, 2013, Oracle and/or its affiliates. All rights reserved.

Primary Author: Rajesh Gouthaman

Contributing Authors: Srinivas Sudhindra, Kumar Dhanagopal

Contributors: Amit Gupta, Nagakishore Sidde, Isvaran Krishnamurthy, Basant Kukreja

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, the following notice is applicable:

U.S. GOVERNMENT RIGHTS Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, duplication, disclosure, modification, and adaptation shall be subject to the restrictions and license terms set forth in the applicable Government contract, and, to the extent applicable by the terms of the Government contract, the additional rights set forth in FAR 52.227-19, Commercial Computer Software License (December 2007). Oracle USA, Inc., 500 Oracle Parkway, Redwood City, CA 94065.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle is a registered trademark of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners.

This software and documentation may provide access to or information on content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

Contents

Preface	ix
Audience.....	ix
Documentation Accessibility	ix
Related Documents	ix
Conventions	x
 1 Overview of the Oracle Traffic Director Command-Line Interface	
1.1 General Syntax	1-1
1.2 Usage Modes	1-1
1.2.1 Standalone Mode	1-2
1.2.2 Shell Mode	1-2
1.2.3 File Mode	1-2
1.3 Security	1-2
1.4 Command-Line Interface Utilities	1-3
1.4.1 Short Name Option	1-3
1.4.2 Tab Completion.....	1-3
1.5 Error Messages	1-4
1.6 List of Commands.....	1-4
 2 Oracle Traffic Director CLI Commands	
block-proxy-info.....	2-2
configure-server	2-4
copy-config.....	2-6
copy-virtual-server	2-7
create-cache-rule	2-8
create-cert-request.....	2-9
create-compression-rule.....	2-11
create-config.....	2-12
create-error-page	2-14
create-event	2-15
create-failover-group	2-17
create-http-listener	2-19
create-instance	2-21

create-origin-server.....	2-22
create-origin-server-pool	2-23
create-request-limit.....	2-25
create-route	2-26
create-selfsigned-cert.....	2-27
create-tcp-listener.....	2-29
create-tcp-proxy	2-31
create-variable	2-32
create-virtual-server	2-33
delete-cache-rule	2-35
delete-cert.....	2-36
delete-compression-rule.....	2-37
delete-config	2-38
delete-crl.....	2-39
delete-error-page.....	2-40
delete-event.....	2-41
delete-failover-group.....	2-43
delete-http-listener.....	2-45
delete-instance	2-46
delete-origin-server.....	2-47
delete-origin-server-pool	2-48
delete-request-limit.....	2-49
delete-route	2-50
delete-tcp-listener.....	2-51
delete-tcp-proxy	2-52
delete-variable	2-53
delete-virtual-server	2-54
delete-webapp-firewall-ruleset.....	2-55
deploy-config.....	2-56
disable-access-log.....	2-57
disable-admin-ldap-auth	2-58
disable-ciphers.....	2-59
disable-event.....	2-60
disable-perfdump.....	2-62
disable-route-auth.....	2-63
disable-services.....	2-64
disable-stats-xml	2-65
disable-tcp-access-log.....	2-66
disable-webapp-firewall	2-67
enable-access-log.....	2-68
enable-admin-ldap-auth	2-69
enable-ciphers.....	2-71

enable-event.....	2-72
enable-perfdump.....	2-74
enable-route-auth.....	2-75
enable-services.....	2-76
enable-stats-xml.....	2-77
enable-tcp-access-log.....	2-78
enable-webapp-firewall.....	2-79
forward-proxy-info.....	2-80
get-access-log.....	2-82
get-access-log-buffer-prop.....	2-84
get-access-log-prop.....	2-85
get-admin-ldap-auth-prop.....	2-86
get-admin-prop.....	2-87
get-cache-prop.....	2-89
get-cache-rule-prop.....	2-90
get-cert-prop.....	2-92
get-compression-rule-prop.....	2-94
get-config-file.....	2-96
get-config-prop.....	2-97
get-config-stats.....	2-98
get-crl-prop.....	2-99
get-dns-cache-prop.....	2-100
get-dns-prop.....	2-101
get-failover-group-prop.....	2-102
get-health-check-prop.....	2-103
get-http-listener-prop.....	2-104
get-http-prop.....	2-106
get-keep-alive-prop.....	2-107
get-localization-prop.....	2-109
get-log.....	2-110
get-log-prop.....	2-112
get-origin-server-pool-prop.....	2-113
get-origin-server-prop.....	2-114
get-origin-server-stats.....	2-116
get-perfdump.....	2-117
get-perfdump-prop.....	2-118
get-pkcs11-prop.....	2-119
get-qos-limits-prop.....	2-120
get-qos-prop.....	2-121
get-request-limit-prop.....	2-122
get-route-auth-prop.....	2-123

get-route-prop	2-124
get-snmp-prop	2-126
get-ssl-prop	2-127
get-ssl-session-cache-prop	2-129
get-stats-prop	2-130
get-stats-xml.....	2-131
get-stats-xml-prop.....	2-132
get-tcp-access-log	2-133
get-tcp-access-log-prop	2-134
get-tcp-listener-prop	2-135
get-tcp-proxy-prop.....	2-137
get-tcp-proxy-stats	2-138
get-tcp-thread-pool-prop	2-139
get-thread-pool-prop	2-140
get-virtual-server-prop.....	2-141
get-virtual-server-stats	2-143
get-webapp-firewall-prop.....	2-144
help.....	2-145
install-cert.....	2-151
install-crl.....	2-153
install-webapp-firewall-ruleset.....	2-154
list-backups	2-155
list-cache-rules	2-156
list-certs.....	2-157
list-ciphers	2-158
list-compression-rules	2-159
list-configs	2-160
list-config-files	2-161
list-crls.....	2-162
list-error-pages	2-163
list-events	2-164
list-failover-groups	2-165
list-http-listeners	2-166
list-instances.....	2-167
list-nodes	2-168
list-origin-servers	2-169
list-origin-server-pools	2-170
list-proxy-info	2-171
list-request-limits	2-172
list-routes.....	2-173
list-tcp-listeners	2-174
list-tcp-proxies	2-175

list-tokens	2-176
list-variables.....	2-177
list-virtual-servers.....	2-178
list-webapp-firewall-rulesets.....	2-179
pull-config.....	2-180
reconfig-instance	2-181
remove-node.....	2-182
renew-admin-certs	2-183
renew-node-certs.....	2-184
reset-admin-password.....	2-185
restart-admin	2-186
restart-instance	2-187
restore-config.....	2-188
rotate-log	2-189
set-access-log-buffer-prop	2-190
set-admin-prop.....	2-192
set-cache-prop.....	2-194
set-cache-rule-prop	2-196
set-cert-trust-prop	2-198
set-compression-rule-prop	2-200
set-config-file	2-202
set-config-prop	2-203
set-dns-cache-prop.....	2-205
set-dns-prop.....	2-207
set-failover-group-primary.....	2-209
set-health-check-prop	2-210
set-http-listener-prop.....	2-212
set-http-prop	2-215
set-keep-alive-prop	2-217
set-localization-prop	2-219
set-log-prop	2-220
set-origin-server-pool-prop	2-222
set-origin-server-prop	2-224
set-pkcs11-prop	2-226
set-qos-limits-prop	2-228
set-qos-prop	2-230
set-request-limit-prop.....	2-231
set-route-prop	2-233
set-snmp-prop	2-236
set-ssl-prop.....	2-238
set-ssl-session-cache-prop.....	2-240

set-stats-prop	2-242
set-tcp-listener-prop	2-243
set-tcp-proxy-prop	2-245
set-tcp-thread-pool-prop	2-247
set-thread-pool-prop	2-249
set-token-pin	2-251
set-token-prop	2-252
set-virtual-server-prop	2-254
start-failover	2-256
start-instance	2-257
start-snmp-subagent	2-258
stop-admin	2-260
stop-failover	2-261
stop-instance	2-262
stop-snmp-subagent	2-263
unconfigure-server	2-264

Preface

This document describes the Oracle Traffic Director command-line interface (CLI).

Audience

This book is intended for Oracle Traffic Director administrators. This book assumes you are familiar with the following topics:

- Installing software
- Performing basic system administration tasks
- Issuing commands in a terminal window

Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc>.

Access to Oracle Support

Oracle customers have access to electronic support through My Oracle Support. For information, visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info> or visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs> if you are hearing impaired.

Related Documents

For more information, see the following documents, which are available on the Oracle Technology Network:

- *Oracle Traffic Director Administrator Guide*
- *Oracle Traffic Director Configuration File Reference*
- *Oracle Traffic Director Installation Guide*
- *Oracle Virtual Assembly Builder User's Guide*
- *Oracle VM Manager User's Guide*
- *Oracle Exalogic Elastic Cloud Documentation*

Conventions

The following text conventions are used in this document:

Convention	Meaning
boldface	Boldface type indicates graphical user interface elements associated with an action, or terms defined in text or the glossary.
<i>italic</i>	Italic type indicates book titles, emphasis, or placeholder variables for which you supply particular values.
<code>monospace</code>	Monospace type indicates commands within a paragraph, URLs, code in examples, text that appears on the screen, or text that you enter.

Overview of the Oracle Traffic Director Command-Line Interface

This chapter provides an overview of the general syntax, usage modes, CLI (Command-Line Interface) commands, common options, variables, security, and error messages that are relevant to Oracle Traffic Director.

1.1 General Syntax

The general syntax provides the command name, common options, and mandatory options, followed by the operand. All options start with the (--) notation. The short option names must be prefixed with the (-) notation. Non-mandatory options are indicated by []. For more information about common options, see [help](#).

Example for options:


```
$tadm --user=admin --port=1895
```

Example for short options:

```
$tadm -u admin -p 1895
```

An example of general syntax is provided below.

Figure 1–1 CLI Syntax



1.2 Usage Modes

This section provides information on the command-line modes of Oracle Traffic Director, including Standalone mode, Shell mode, and File mode.

1.2.1 Standalone Mode

In the standalone mode option, users invoke the CLI (`tadm`) from a command shell by specifying the command, options, and operands. Once the command is executed, the CLI exits to the shell. For more information, see [help](#).

Example:

```
$tadm create-config --user=admin --password-file=./admin.pwd
--listener-port=2222 --server-name=syrinx myconfig

CLI201 Command 'create-config' ran successfully.
```

1.2.2 Shell Mode

In the shell mode option, users invoke CLI (`tadm`) from a command shell by not entering the command. The CLI prompts users to enter a command. Once the command is executed, the control returns to the `tadm` shell. The shell can be exited by typing `exit` or `quit` command. For more information, see [help](#).

Example:

```
$tadm --user=admin --password-file=./admin.pwd --host=admin.example.com
--port=8989
OTD 1.0 B06/07/2011 09:40
tadm> list-configs
www.example.com
soa.example.org
tadm> exit
$
```

Note: Shell mode does not support non-ASCII character input. However, it is supported in standalone mode.

1.2.3 File Mode

In the file mode option, users specify the commands file which contains a list of valid commands.

Example:

```
$tadm --user admin --password-file ./admin.pwd --host=localhost
--port 8888 --commands-file file.txt
```

1.3 Security

Guidelines for entering the user name and password while performing tasks in the CLI is provided below. User name and password must be used in accordance with the policies that are defined in Oracle Traffic Director application. While performing multiple tasks in the CLI, user name and password must be used in the following combinations:

- The user name and password must be entered for each user command running in a standalone mode.

Example:

```
$tadm list-configs --user=admin --password-file=./admin.pwd
--host=admin.example.com --port=8888
```

- While performing tasks in the shell mode, user name and password file are accepted when `tadm` executable is invoked. The user name and password file options may not be entered while the user commands are invoked in the shell mode.

Example:

```
$tadm --user=admin --host=admin.example.com --port=8888
Enter the password>
tadm>
```

- Oracle recommends that the password file be provided in read-only mode to the administrator and not stored on NFS or a shared disk. The contents of the password file must be provided as
`tadm_password=password`
- The password file can contain multiple passwords. For example,
`tadm_password=<password>`
`tadm_token-pin=<pin>`

If a `tadm` command requires password and it is not provided in the password file, the user will be prompted for the password

Note: File mode is similar to the shell mode.

1.4 Command-Line Interface Utilities

Some of the command-line utilities that Oracle Traffic Director supports are described in this section.

1.4.1 Short Name Option

When you execute `tadm` commands, you can use short names of the boolean options as a standalone option.

Example: `-e`, `-v` and `-p` can be combined and used as `-evp`

Note: You can specify options in any order without any change in the functional behavior of the command.

1.4.2 Tab Completion

Tab completion is a `tadm` feature. The Tab key must be pressed twice to autocomplete `tadm` commands and their options. For `tadm` options, if you type "--" and press the Tab key twice, the `tadm` shell will list the available options of a particular command. If you type "--c" and press the Tab key twice, the `tadm` shell will attempt to complete the option if there are no other options starting with c. If there are any options, they will be listed.

Example:

```
$ tadm
$ tadm p<tab><tab>
$ tadm pull-config
```

1.5 Error Messages

The general format that is used while specifying errors and warnings are described below.

CLI<Error-code>: <Error Message>

Example:

CLI004: Required option --vs not found in the command. Please run the command again with --vs option.

For more information about the error codes and their description, see [help](#).

1.6 List of Commands

This section contains the functional list of CLI commands that are used in Oracle Traffic Director. Using this section you can look for specific commands based on the functional role of Oracle Traffic Director.

Instance Root Configuration

- [configure-server](#)
- [unconfigure-server](#)

Configuration Management

- [create-config](#)
- [delete-config](#)
- [list-configs](#)
- [copy-config](#)
- [deploy-config](#)
- [pull-config](#)
- [list-config-files](#)
- [get-config-file](#)
- [set-config-file](#)
- [list-backups](#)
- [restore-config](#)

Listener Management

- [create-http-listener](#)
- [delete-http-listener](#)
- [list-http-listeners](#)
- [get-http-listener-prop](#)
- [set-http-listener-prop](#)
- [set-origin-server-pool-prop](#)

Server Pool Management

- [create-origin-server-pool](#)

- [delete-origin-server-pool](#)
- [list-origin-server-pools](#)
- [get-origin-server-pool-prop](#)

Health Check

- [get-health-check-prop](#)
- [set-health-check-prop](#)

Origin Server

- [create-origin-server](#)
- [delete-origin-server](#)
- [list-origin-servers](#)
- [get-origin-server-prop](#)
- [set-origin-server-prop](#)

Configuration Properties

- [get-config-prop](#)
- [set-config-prop](#)

Localization Properties

- [get-localization-prop](#)
- [set-localization-prop](#)

HTTP Properties

- [get-http-prop](#)
- [set-http-prop](#)

Keep-Alive

- [get-keep-alive-prop](#)
- [set-keep-alive-prop](#)

Thread Pool

- [get-thread-pool-prop](#)
- [set-thread-pool-prop](#)

Quality of Service (QoS)

- [get-qos-prop](#)
- [set-qos-prop](#)

Domain Name Service

- [get-dns-prop](#)
- [set-dns-prop](#)

Domain Name Service Cache

- [get-dns-cache-prop](#)
- [set-dns-cache-prop](#)

SSL Session Cache

- [get-ssl-session-cache-prop](#)
- [set-ssl-session-cache-prop](#)

Access Log Buffer Properties

- [get-access-log-buffer-prop](#)
- [set-access-log-buffer-prop](#)

Variables

- [create-variable](#)
- [delete-variable](#)
- [list-variables](#)

Proxy Cache

- [get-cache-prop](#)
- [set-cache-prop](#)

Virtual Server Management

- [create-virtual-server](#)
- [delete-virtual-server](#)
- [list-virtual-servers](#)
- [get-virtual-server-prop](#)
- [set-virtual-server-prop](#)
- [copy-virtual-server](#)

(QoS) Limits

- [get-qos-limits-prop](#)
- [set-qos-limits-prop](#)

Error Page Settings

- [create-error-page](#)
- [delete-error-page](#)
- [list-error-pages](#)

Rules Management

- [create-route](#)
- [delete-route](#)
- [list-routes](#)
- [get-route-prop](#)
- [set-route-prop](#)
- [enable-route-auth](#)
- [disable-route-auth](#)
- [get-route-auth-prop](#)
- [list-proxy-info](#)
- [forward-proxy-info](#)

- [block-proxy-info](#)

Proxy Cache Rules

- [create-cache-rule](#)
- [delete-cache-rule](#)
- [list-cache-rules](#)
- [get-cache-rule-prop](#)
- [set-cache-rule-prop](#)

Request Limit Rules

- [create-request-limit](#)
- [delete-request-limit](#)
- [list-request-limits](#)
- [get-request-limit-prop](#)
- [set-request-limit-prop](#)

Compression Rules

- [create-compression-rule](#)
- [delete-compression-rule](#)
- [list-compression-rules](#)
- [get-compression-rule-prop](#)
- [set-compression-rule-prop](#)

SSL

- [get-ssl-prop](#)
- [set-ssl-prop](#)

Ciphers

- [enable-ciphers](#)
- [disable-ciphers](#)
- [list-ciphers](#)

PKCS11

- [get-pkcs11-prop](#)
- [set-pkcs11-prop](#)
- [list-tokens](#)
- [set-token-prop](#)
- [set-token-pin](#)

Certificate Management

- [install-cert](#)
- [delete-cert](#)
- [list-certs](#)
- [get-cert-prop](#)

- [set-cert-trust-prop](#)
- [create-selfsigned-cert](#)
- [create-cert-request](#)

Certificate Revocation List

- [install-crl](#)
- [delete-crl](#)
- [list-crls](#)
- [get-crl-prop](#)

Monitoring

- [get-log](#)
- [get-access-log](#)
- [get-config-stats](#)
- [get-virtual-server-stats](#)
- [get-stats-xml](#)
- [get-perfdump](#)

Error Log

- [get-log-prop](#)
- [set-log-prop](#)

Access Log

- [enable-access-log](#)
- [disable-access-log](#)
- [get-access-log-prop](#)

Stats XML Configuration

- [enable-stats-xml](#)
- [disable-stats-xml](#)
- [get-stats-xml-prop](#)

Perfdump Configuration

- [enable-perfdump](#)
- [disable-perfdump](#)
- [get-perfdump-prop](#)

SNMP

- [get-snmp-prop](#)
- [set-snmp-prop](#)
- [start-snmp-subagent](#)
- [stop-snmp-subagent](#)

Stats

- [get-stats-prop](#)

- [set-stats-prop](#)

Events

- [create-event](#)
- [enable-event](#)
- [disable-event](#)
- [delete-event](#)
- [list-events](#)

Instance Management

- [create-instance](#)
- [delete-instance](#)
- [list-instances](#)
- [start-instance](#)
- [stop-instance](#)
- [restart-instance](#)
- [reconfig-instance](#)
- [rotate-log](#)

Administration Server and Node Management

- [list-nodes](#)
- [get-admin-prop](#)
- [set-admin-prop](#)
- [reset-admin-password](#)
- [restart-admin](#)
- [stop-admin](#)
- [remove-node](#)
- [enable-admin-ldap-auth](#)
- [disable-admin-ldap-auth](#)
- [get-admin-ldap-auth-prop](#)
- [renew-admin-certs](#)
- [renew-node-certs](#)

High Availability

- [create-failover-group](#)
- [delete-failover-group](#)
- [list-failover-groups](#)
- [get-failover-group-prop](#)
- [set-failover-group-primary](#)

Oracle Traffic Director CLI Commands

This chapter lists and describes the CLI user commands and their options for Oracle Traffic Director in alphabetical order.

block-proxy-info

Syntax

```
tadm block-proxy-info common_options --config=config_name --vs=vs_name  
--route=route_name (param)
```

Description

Use this command to block proxy information.

Options

For information about `common_options`, run the [help](#) command.

`--config|-c`

Specify the configuration for which you want to block the proxy parameter.

`--vs|-s`

Specify the name of the virtual server for which you want to block the proxy parameter.

`--route|-r`

Specify the name of the route to block the proxy parameter.

Operands

Specify the name of the proxy parameter you want to block.

`jroute`

`via`

`ip`

`cipher`

`proxy-agent`

`proxy-auth`

`keysize`

`secret-keysize`

`ssl-id`

`issuer-dn`

`user-dn`

`auth-cert`

`xforwarded-for`

`cache-info`

`ssl`

Example

```
tadm block-proxy-info --user=admin --host=admin.example.com  
--password-file=./admin.passwd --port=8989  
--no-prompt --config=www.example.org --vs=soa.example.org
```

```
--route=route1 jroute
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [list-proxy-info](#), [forward-proxy-info](#)

configure-server

Syntax

```
tadm configure-server common_options [--admin-node]
[--node-host=node_host] [--node-port=node_port]
[--server-user=admin_server_user] [--bind-ip=bind_ip] [--java-home=java_home]
--instance-home=instance_home
```

Description

Use this command to create the administration server and administration nodes. Before you create an administration node, make sure that the administration server is running. The newly created administration node will be registered with the administration server.

Note: If `configure-server` is executed as a privileged user, then services are enabled on the server by default.

Options

For information about `common_options`, run the [help](#) command.

`--admin-node|-n`

This option specifies that the command should create an administration node.

`--node-host|-H`

Indicates the host name of the administration node.

`--node-port|-P`

Indicates the SSL port of the administration node.

`--server-user|-r`

Specifies the administrator server user.

`--java-home|-j`

Specifies the Java home directory.

`--instance-home|-i`

Specifies the absolute path name of the directory in which the configuration files and binaries pertaining to the administration server or administration node should be created.

`--bind-ip|-b`

While configuring the administration server, it is used as an ip value for the administration server's default listener. While configuring administration node, it is used as a remote administration server's bind-ip to the administration node.

Example

To configure the administration server:

```
tadm configure-server --instance-home=/home/otd
```

Note: The command prompts you to specify the administrator password.

To configure the administration node:

```
tadm configure-server --user=admin --admin-node --host=admin.example.com
--instance-home=/home/otd
```

Note: The command prompts you for the administration server password.

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [unconfigure-server](#), [list-nodes](#)

copy-config

Syntax

```
tadm copy-config common_options --config=config_name copy_name
```

Description

Use this command to create a copy of an existing configuration. The newly copied configuration is identical to the existing configuration. However, the new configuration does not have any instances even though the configuration from which it has been copied has instances.

Options

For information about *common_options*, run the [help](#) command.

`--config|-c`

Specify the name of the configuration to be copied.

Operands

copy-name

Specify the name of the configuration that you want to copy

Example

```
tadm copy-config --user=admin --password-file=./admin.passwd  
--host=admin.example.com --port=8989 --no-prompt  
--config=www.example.org Config-1
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-config](#), [delete-config](#), [list-configs](#), [deploy-config](#), [pull-config](#)

copy-virtual-server

Syntax

```
tadm copy-virtual-server common_options --config=config_name  
--vs=source_virtual_server_name new_virtual_server_name
```

Description

Use this command to create a copy of an existing virtual-server.

Options

For information about *common_options*, run the [help](#) command.

--config|-c

Specify the configuration for which you want to copy an existing virtual-server.

--vs|-s

Specify the name of the source virtual server.

Operands

new-virtual-server-name

Specify the name of the virtual server that you want to create.

Example

```
tadm copy-virtual-server --user=admin --host=admin.example.com  
--password-file=./admin.passwd --port=8989  
--no-prompt --config=www.example.org --vs=soa.example.org  
virtual-server-1
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-virtual-server](#), [set-virtual-server-prop](#), [delete-virtual-server](#),
[get-virtual-server-prop](#), [list-virtual-servers](#)

create-cache-rule

Syntax

```
tadm create-cache-rule common_options --config=config_name  
--vs=vs_name [--condition=expr] cache_rule_name
```

Description

Use this command to create a cache rule.

Options

For information about `common_options`, run the [help](#) command.

`--config|-c`

Specify the name of the configuration for which you want to create a cache rule.

`--vs|-s`

Specify the virtual server.

`--condition|-C`

Specify the condition for creating the cache rule.

Operands

`cache-rule-name`

Specify the cache rule name.

Example

```
tadm create-cache-rule --user=admin --password-file=./admin.passwd  
--host=admin.example.com --port=8989 --no-prompt  
--config=www.example.org --vs=soa.example.org cache-rule-1
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [delete-cache-rule](#), [get-cache-prop](#), [get-cache-rule-prop](#), [list-cache-rules](#)

create-cert-request

Syntax

```
tadm create-cert-request common_options [--key-type=rsa|ecc] ([--key-size=size] |
[--curve=curve_name]) [--org=org]
[--org-unit=org_unit] [--locality=place] [--state=name]
[--country=name] --config=config_name --token=name
--server-name=[dns_name,...]
```

Description

Use this command to create a new certificate request. A certificate consists of digital data that specifies the name of an individual, company, or other entity, and certifies that the public key included in the certificate belongs to that entity. Both clients and servers can have certificates.

A certificate is issued and digitally signed by a (CA) Certificate Authority. The CA can be a company that sells certificates over the Internet, or it can be a department responsible for issuing certificates for your company's intranet or extranet. You decide which CAs you trust enough to serve as verifiers of other user's identities. The `create-cert-request` command prompts for a token password if the token is password protected.

When you choose the `key-size` as `rsa`, specify the key size. When you choose the `key-type` as `ecc`, specify the name for the curve. The `key-size` and `curve` options in the command are mutually exclusive.

Options

For information about `common_options`, run the [help](#) command.

`--key-type|-k`

Specify the type of the certificate key. The key types can be `rsa` or `ecc`, where:

- `rsa` is an internet encryption and authentication system using public and private keys.
- `ecc` (elliptic curve cryptography) is a public key encryption technique. It is based on the elliptic curve theory that enables security with smaller key sizes. This results in faster computations, lower power consumption, as well as memory and bandwidth savings

`--key-size|-z`

Specify the size of the certificate key. This option is applicable if you choose the `key-type` as `rsa`. The key size can be 1024, 2048, or 4098.

`--curve|-r`

Specify the name of the curve. This option is applicable if you choose the `key-type` as `ecc`.

`--org|-g`

Specify the name of your organization, company, or educational institution.

`--org-unit|-o`

Enter a description of an organizational unit within your company.

`--locality|-l`

Enter a description of the city, principality, or country of the organization.

`--state|-a`

Specify the state or province where your organization is located.

`--country|-y`

Specify a two-character abbreviation of your country's name (in ISO format). For example, the country code for the United States is US.

`--config|-c`

Specify the name of the configuration for which you want to create the certificate.

`--token|-t`

Specify the token (cryptographic device) name, which contains the encrypted public key.

`--server-name|-s`

Specify the host name of the server for which you are requesting a certificate from the CA.

Note: The property `server-name` enables you to specify multiple values, with each value enclosed in quotes and separated by commas.

Example

When you choose `key-type` as `rsa`

```
tadm create-cert-request --user=admin --host=admin.example.com
--password-file=./admin.passwd --port=8989
--no-prompt --key-size=2048 --org=ora --country=IN
--locality=abc --config=www.example.org --token=internal --server-name=config1.org
```

When you choose `key-type` as `ecc`

```
tadm create-cert-request --user=admin --host=admin.example.com
--password-file=./admin.passwd --port=8989
--no-prompt --curve=certificate_manager --org=ora --country=IN
--locality=abc --config=www.example.org --token=internal
--server-name=config2.org
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [install-cert](#), [list-certs](#), [delete-cert](#), [get-cert-prop](#), [set-cert-trust-prop](#)

create-compression-rule

Syntax

```
tadm create-compression-rule common_options
[--condition=expr] --config=config_name --vs=vs_name
compression_rule_name
```

Description

Use this command to create a compression rule.

Options

For information about *common_options*, run the [help](#) command.

--condition|-C

Specify the condition for the compression rule.

--config|-c

Specify the configuration name for which you want to create a compression rule.

--vs|-s

Specify the name of the virtual server.

Operands

create-compression-rule

Specify the compression rule name.

Example

```
tadm create-compression-rule --user=admin --host=admin.example.com
--password-file=./admin.passwd --port=8989
--no-prompt --config=www.example.org --vs=soa.example.org
compression-rule-1
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [delete-compression-rule](#), [set-compression-rule-prop](#), [list-compression-rules](#)

create-config

Syntax

```
tadm create-config common_options [--server-user=user_id]  
[--ip=ip] --server-name=server_name [--origin-server-type=http/https/tcp]  
--listener-port=port --origin-server=host:port[,host:port,...] config_name
```

Description

Use this command to create a new configuration that listens to HTTP and TCP traffic on a given port and front-ends a set of HTTP and TCP origin servers. By using this command, you can create a default virtual server that handles HTTP traffic and a default tcp proxy that handles TCP traffic. In addition, it creates a default route and forwards all traffic to the origin server.

Options

For information about `common_options`, run the [help](#) command.

`--server-user | -r`

Specify the user ID of a server user, for example, *root*. This option is mandatory if the administration server is on UNIX.

`--ip | -I`

Specify the Internet Protocol (IP) address for the default listener. If you provide the IP address, the server will bind to the IP address for the default listener. Only traffic sent to this IP address will be serviced.

`--listener-port | -`

Specify the listener port details for creating the configuration.

`--origin-server-type |`

Specify the type of requests handled by the origin servers.

`--server-name | -s`

Specify the host name of the server.

`--origin-server | -O`

Specify the comma separated list of origin servers of the format `host:port`. If the origin server is specified and the origin server port is 80, the port need not be specified. For example: `os1.example.com` and `os2.example.com`

Note: The property `origin-server` enables you to specify multiple values, with each value enclosed in quotes and separated by commas.

Operands

`config-name`

Specify the name of the configuration that you want to create. Configuration name should not contain spaces, invalid characters or non-ASCII characters.

Example

Creating a configuration with an HTTP listener.

```
tadm create-config --user=admin --password-file=./admin.passwd
--host=admin.example.com --port=8989 --no-prompt
--listener-port=18022 --server-name=test1
--origin-server=www.mail.com,www.hotmail.com:8081
config-1
```

Creating a configuration with a TCP listener.

```
tadm create-config --user=admin --password-file=./admin.passwd
--host=admin.example.com --port=8989 --no-prompt
--listener-port=8080 --origin-server=www.mail.com,www.hotmail.com:8081
config-1
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [list-backups](#), [list-configs](#), [delete-config](#), [copy-config](#), [pull-config](#), [restore-config](#), [list-config-files](#), [get-config-file](#), [set-config-file](#), [deploy-config](#)

create-error-page

Syntax

```
tadm create-error-page common_options --config=config_name --vs=vs_name  
--code=error_code --error-page=error_page
```

Description

Use this command to create an error page.

Options

For information about `common_options`, run the [help](#) command.

`--config|-c`

Specify the name of the configuration for which you want to create an error page.

`--vs|-v`

Specify the name of the virtual server.

`--code|-d`

Specify the error code for which you want to create an error page. Range is between 400 to 599

`--error-page|-g`

Specify the absolute path for which you want to create an error page.

Example

```
tadm create-error-page --user=admin --password-file=./admin.passwd  
--host=admin.example.com --port=8989 --no-prompt  
--no-enabled=true --config=www.example.org --vs=soa.example.org  
--code=408 --error-page=/documents/otd
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [delete-error-page](#), [list-error-pages](#)

create-event

Syntax

```
tadm create-event common_options [--no-enabled] --config=config_name
--command=restart|reconfig|rotate-log|rotate-access-log|update-crl|commandline
((--time=hh:mm [--month=1-12]
[--day-of-week=sun|mon|tue|wed|thu|fri|sat] [--day-of-month=1-31]) |
--interval=number_of_seconds))
```

Description

Use this command to create a new event. Additionally, you can set a specific time and interval for scheduling automatic instance reconfiguration. You can also create an event to restart and reconfigure all running instances, rotate access and error logs, and update the certificate revocation list. Also, you can provide the absolute path to a file to be executed.

Options

For information about *common_options*, run the [help](#) command.

--no-enabled|-n

Specify this option to disable the event at runtime.

--config|-c

Specify the name of the configuration for which you want to create the event.

--command|-C

Specify the command that the event executes. The value can be *restart*, *reconfig*, *rotate-log*, *rotate-access-log*, and *update-crl*, or any executable command.

--time|-t

Specify the time, for example, 12:30, when you want this event to start. The format of the time is *hh:mm*.

--month|-m

Specify the month when you want this event to occur. The range of values is 1 to 12.

--day-of-week|-k

Specify the day of the week when you want this event to occur. The values can be *Sun*, *Mon*, *Tue*, *Wed*, *Thu*, *Fri*, or *Sat*.

--day-of-month|-d

Specify the day of the month when you want this event to occur. The range of values is 1 to 31.

--interval|-r

Specify the time interval at which you want this event to occur. The range of values is 60 to 86400 seconds.

Example

```
tadm create-event --user=admin --password-file=./admin.passwd
--host=admin.example.com --port=8989 --no-prompt
--no-enabled=true --config=www.example.org --command=rotate-log
--interval=120
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [delete-event](#), [list-events](#), [disable-event](#), [enable-event](#)

create-failover-group

Syntax

```
create-failover-group common_options --config=config_name --virtual-ip=VIP
  [--network-prefix-length=number_of_bits] --primary-node=node [--force]
  --backup-node=node [--primary-nic=network_interface]
  [--backup-nic=network_interface] [--router-id=router_id]
```

Description

Use this command to create a failover group consisting of two Oracle Traffic Director instances grouped by a unique virtual IP address (VIP), to provide high availability in active-passive mode. Requests are received at the specified VIP address and routed to the Oracle Traffic Director instance that is designated as the primary instance. If the primary instance is not reachable, requests are routed to the backup instance.

For active-active failover, you should create two failover groups, both consisting of the same two nodes, but with the primary and backup roles reversed. Each instance is the primary instance for one VIP address and the backup for the other VIP.

There can be a maximum of 255 failover groups, across configurations.

When creating a failover group, if the administration node process is running as non-root on the node where the instances are located, then you must run [start-failover](#) on those nodes as a root user. This is to manually start the failover. If this command is not executed, failover will not start and there will be no high availability.

For more information about how failover works in Oracle Traffic Director, see the *Oracle Traffic Director Administrator's Guide* on OTN.

Options

For information about *common_options*, run the [help](#) command.

--config|-c

The name of the configuration for which you want to create a failover group.

--virtual-ip|-i

A unique virtual IP address (VIP) to identify the failover group.

The VIP can be a host name or an IPv4/IPv6 address. The VIP should belong to the same subnet as that of the nodes in the failover group, and must be accessible to clients.

--network-prefix-length|-z

The network prefix of the interface on which the VIP should be managed.

The network prefix is the subnet mask represented in the Classless Inter-Domain Routing (CIDR) format. For example, for an IPv4 VIP address in a subnet that contains 256 addresses (8 bits), the CIDR notation of the subnet mask 255.255.255.0 would be 24, which is derived by deducting the number of addresses in the given subnet (8 bits) from the maximum number of IPv4 addresses possible (32 bits).

To calculate the CIDR notation of the subnet mask for an IPv6 subnet, deduct the bit-size of the subnet's address space from 128 bits, which is the maximum number of IPv6 addresses possible.

If you do not specify the network prefix, the default of 24 is assumed for an IPv4 VIP, and 64 for an IPv6 VIP.

`--primary-node|-n, --backup-node|-b`

The administration nodes that you want to specify as the primary and backup nodes in the failover group. Both the nodes should be in the same subnet and should be running as the root user. The nodes should not have an instance that is already part of another failover group. Note that the administration nodes that you select need not have Oracle Traffic Director instances running on them.

`--force|-f`

Specify this option to force creation of the failover group even if a failover group already exists with the specified VIP. The existing failover group will be replaced.

`--primary-nic|-m, --backup-nic|-k`

The network interfaces, on the primary and back up node, on which the VIP must be managed. If you do not specify the network interfaces, Oracle Traffic Director discovers them automatically.

`--router-id|-r`

The router ID for the failover group. The value should be unique across failover groups. If you do not specify the router ID, it is set to 255 for the first failover group. For every subsequent failover group that you create, the default router ID is decremented by one: 254, 253, and so on.

Example

```
tadm create-failover-group --config=soa --virtual-ip=10.229.227.80
--primary-node=node1.example.com --backup-node=node2.example.com
```

```
tadm start-failover --user=admin
--password-file=./admin.passwd --host=admin.example.com --port=8989
--no-prompt --config=soa --instance-home=/home/otd
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [delete-failover-group](#), [get-failover-group-prop](#), [set-failover-group-primary](#), [list-failover-groups](#), [start-failover](#), [stop-failover](#)

create-http-listener

Syntax

```
tadm create-http-listener common_options [--no_enabled]
[--ip=address] [--acceptor-threads=count] [--blocking-io=true/false]
[--handle-protocol-mismatch=true/false] [--family=name] [--listen-queue-size=size]
[--receive-buffer-size=size]
[--send-buffer-size=size] [--description=text] --listener-port=number
--config=config_name --server-name=server_name --default-virtual-server=vs_name
listener_name
```

Description

Use this command to create a new HTTP listener socket. All virtual servers have an HTTP listener specified. When a new request comes in, Oracle Traffic Director determines which virtual server to send it to, based on the configured HTTP listener.

Options

For information about *common_options*, run the [help](#) command.

`--no-enabled|-n`

Specify this option if you want to disable the HTTP listener at runtime.

`--ip|-I`

Indicates the IP address of the host computer. Specify an asterisk (*) for the HTTP listener to listen to all the available IP addresses on the host computer.

`--acceptor-threads|-a`

Specify the number of threads dedicated to accept the connections received by this listener. The range of values is 1 to 128.

`--blocking-io|-b`

If you specify this option, the HTTP listener socket is in the blocking mode.

`--handle-protocol-mismatch|-m`

If you specify this option, the server responds to Secure Sockets Layer (SSL) or non-SSL protocol mismatches in client requests with an HTTP redirect or SSL alert. The default is `true`, meaning that the server attempts to detect SSL or non-SSL protocol mismatches and send an HTTP redirect or SSL alert when a mismatch is detected.

`--family|-f`

Specify the internet protocol family, for example: `IPv4`, and `IPv6`. The default is `IPv4` (`family=inet`). To use the `IPv6` address, specify `family=inet6`.

`--listen-queue-size|-l`

Specify the size (in bytes) of the operating system listen queue back log. The range of values is 1 to 65536.

`--receive-buffer-size|-r`

Specify the size (in bytes) of the operating system socket receive buffer. The range of values is 1 to 1048576.

`--send-buffer-size|-B`

Specify the size (in bytes) of the operating system socket send buffer. The range of values is 1 to 1048576.

`--description|-D`

Enter a description of the HTTP listener.

`--listener-port|-P`

Specify the port number where the configuration binds to and listens for requests. The range of values is 1 to 65535.

`--config|-c`

Specify the name of the configuration for which you want to create the new HTTP listener socket.

`--server-name|-s`

Specify the name of the default server.

`--default-virtual-server-name|-d`

Specify the name of the default virtual server that processes requests that do not match a `host-pattern`. `host-pattern` defines a list of hosts to be added to the new virtual server. To specify multiple URLs, separate them by a comma (,).

Operands

`listener-name`

Specify the name of the HTTP listener that you want to create.

Example

```
tadm create-http-listener --user=admin --host=admin.example.com
--password-file=./admin.passwd --port=8989
--no-prompt --listener-port=18033
--config=www.example.org --server-name=config1.com
--default-virtual-server-name=config1
http-listener-1
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [set-http-listener-prop](#), [list-http-listeners](#), [delete-http-listener](#)

create-instance

Syntax

```
tadm create-instance common_options [--force] --config=config_name (node_host) +
```

Description

Use this command to create an instance of Oracle Traffic Director. Instance refers to the environment of a Oracle Traffic Director daemon on a given node, including its configuration, log files, and other runtime artifacts such as lock databases, caches, and temporary files. A node is a network resource, such as a server or a host. In a typical data center, a network of nodes is called a server farm.

Note: If the node is service-enabled, when you create a new instance, a service is also created for that instance.

Options

For information about *common_options*, run the [help](#) command.

--force|-f

Specify this option to enable a forced creation of an instance. Providing this option deletes any existing instance for the specified configuration on the specified node before creating the instance.

--config|-c

Specify the name of the configuration for which you want to create the instance.

Operands

node-host

Specify the name of the node.

Example

```
tadm create-instance --user=admin --password-file=./admin.passwd
--host=admin.example.com --port=8989 --no-prompt
--config=www.example.org serverhost
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [delete-instance](#), [list-instances](#), [start-instance](#), [stop-instance](#), [restart-instance](#), [reconfig-instance](#), [list-nodes](#), [list-nodes](#), [remove-node](#)

create-origin-server

Syntax

```
tadm create-origin-server common_options [--backup=true/false]
[--ramp-up-time=number_of_seconds]
[--max-connections=number_of_connections]
--config=config_name --origin-server-pool=origin_server_pool_name host:port
```

Description

Use this command to create a origin pool server to the existing origin server pool. The origin server defines a member of a server pool.

Options

For information about *common_options*, run the [help](#) command.

--backup|-b

When you specify this option, the Oracle Traffic Director sends requests to this origin server only when none of the primary (non-backup) origin servers is available.

--ramp-up-time|-r

The time taken by the application to expedite the sending rate to match the newly set up origin server. The range of values is 0.001 to 3600.

--max-connections|-x

Specify the maximum number of concurrent connections to a server. The range of values is 1 to 1048576.

--config|-c

Specify the name of the configuration for which you want to create origin server.

Note: For origin servers of type HTTP and HTTPS, the default port values are provided if they are not specified.

Example

```
tadm create-origin-server --user=admin
--host=admin.example.com --password-file=./admin.passwd
--port=8989 --no-prompt --config=www.example.org
--origin-server-pool=origin-server-pool-1 www.mail.com:8080
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [delete-origin-server](#), [list-origin-servers](#), [get-origin-server-prop](#), [set-origin-server-prop](#)

create-origin-server-pool

Syntax

```
tadm create-origin-server-pool common_options
[--load-distribution=round-robin|least-connection-count|least-response-time]
[--family=default|inet|inet6|inet-sdp]
--type=http|https|tcp --config=config_name
--origin-server=host:port[,host:port,...] origin_server_pool_name
```

Description

Use this command to create a origin-server pool. The origin-server pool configures a pool of origin servers that are used for load balancing requests.

Options

For information about *common_options*, run the [help](#) command.

`--load-distribution|-l`

Specify the load distribution algorithm. Values are round-robin, least-response-time and least-connection-count (default).

`--family|-f`

Specify the internet protocol family, for example:IPV4, and IPV6. The default is IPv4 (`family=inet`). To use the IPv6 address, specify `family=inet6`.

`--type|-t`

Specify the type of requests handled by each server in the server pool, for example: HTTP, HTTPS, TCP.

`--config|-c`

Specify the configuration for which you want to create a origin-server pool.

`--origin-server|-O`

Specify the list of origin servers of the format `host:port` separated by comma. For origin servers of type HTTP and HTTPS, if the port information is not specified, it defaults to 80 and 443 respectively. For origin servers of type TCP, port information is mandatory.

Note: The property `origin-server` enables you to specify multiple values, with each value enclosed in quotes and separated by commas.

Operands

origin-server-pool-name

Specify the name of the origin-server pool.

Example

```
tadm create-origin-server-pool --user=admin --host=admin.example.com
--password-file=./admin.passwd --port=8989
--no-prompt --type=http --config=www.example.org --origin-server=www.mail.com:8080
--load-distribution=least-response-time http-pool-1
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [set-origin-server-pool-prop](#), [get-origin-server-pool-prop](#),
[delete-origin-server-pool](#), [list-origin-server-pools](#)

create-request-limit

Syntax

```
tadm create-request-limit common_options --config=config_name
--vs=vs_name (--max-rps=x | --max-connections=c) [--condition=expr] request_limit_name
```

Description

Use this command to create a request limit rule.

Options

For information about *common_options*, run the [help](#) command.

--config|-c

Specify the name of the configuration for which you want to create a request limit rule.

--vs|-s

Specify the name of the virtual server.

--max-rps|-r

Specify the maximum requests per second.

--max-connections|-x

Specify the maximum number of concurrent connections to a server. Values are 0 or a positive integer. Default: 0. The maximum allowable value is 20480.

--condition|-C

Specify the condition for the request limit.

Operands

request-limit-name

Specify the request limit rule name.

Example

```
tadm create-request-limit --user=admin --host=admin.example.com
--password-file=./admin.passwd --port=8989
--no-prompt --config=www.example.org
--vs=soa.example.org --max-connections=25 request-limit-1
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [delete-request-limit](#), [list-request-limits](#), [get-request-limit-prop](#), [set-request-limit-prop](#)

create-route

Syntax

```
tadm create-route common_options --origin-server-pool=pool_name --config=config_name --vs=vs_name [--condition=expr] route_name
```

Description

Use this command to create a route. Based on the condition specified while creating a route, the load balancing requests are routed to the specified origin-server pool. A default route is created when a virtual-server is created.

Options

For information about `common_options`, run the [help](#) command.

`--origin-server-pool|-o`

Specify the name of the origin-server pool to which the load balancing requests must be routed.

`--config|-c`

Specify the name of the configuration for which you want to create route rule.

`--vs|-s`

Specify the name of the virtual server.

`--condition|-C`

Specify the condition for the route rule.

Operands

`route-name`

Specify the route name.

Example

```
tadm create-route --user=admin --host=admin.example.com  
--password-file=./admin.passwd --port=8989 --no-prompt --config=www.example.org  
--vs=soa.example.org route-1
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [delete-route](#), [list-routes](#), [get-route-prop](#), [set-route-prop](#)

create-selfsigned-cert

Syntax

```
tadm create-selfsigned-cert common_options [--token=name]
[--org-unit=org_unit] [--locality=place] [--state=name]
[--validity=number_of_months] [--org=org] [--country=name]
[--key-type=rsa/ecc] ([--key-size=size] | [--curve=curve_name])
--config=config_name --server-name=[dns_name,...] --nickname=nick_name
```

Description

Use this command to create a new self-signed certificate. The `create-selfsigned-cert` command prompts for a token password if the token is password protected. A self-signed certificate is an identity certificate that is signed by its own creator. In a typical SSL server deployment, if a particular server certificate is valid (contains correct information), it is attested by a digital signature from a Certificate Authority (CA).

Options

For information about `common_options`, run the [help](#) command.

`--token|-t`

Specify the token (cryptographic device) name, which contains the encrypted public key

`--org-unit|-o`

Enter a description of an organizational unit within your company.

`--locality|-l`

Enter a description of the city, principality, or country of the organization.

`--state|-a`

Specify the state or province where the business is located.

`--token-pin|-P`

Specify the Personal Identification Number (PIN) required to initialize the token. You can also define the `token-pin` in the password file.

`--validity|-d`

Specify the validity of the certificate.

`--org|-g`

Enter the official name of your company, educational institution, or organization.

`--country|-y`

Enter a two-character abbreviation of your country's name (in ISO format). For example, the country code for the United States is `US`.

`--key-type|-k`

Specify the type of the certificate key. The key types can be `rsa` or `ecc`. The default key type is `rsa` if this option is not specified.

`--key-size|-z`

Specify the size of the certificate key. This option is applicable only if the `key-type` is `rsa`. The key size can be 1024, 2048, or 4098. The default key size is 2048 if this option is not specified.

`--curve|-r`

Specify the name of the key curve. This option is applicable if you specify the `key-type` as `ecc`. The key curves can be `prime256v1`, `secp256r1`, `nistp256`, `secp256k1`, `secp384r1`, `nistp384`, `secp521r1`, `nistp521`, `sect163k1`, `nistk163`, `sect163r1`, `sect163r2`, `nistb163`, `sect193r1`, `sect193r2`, `sect233k1`, `nistk233k1`, `nistk233`, `sect233r1`, `nistb233`, `sect239k1`, `sect283k1`, `nistk283`, `sect283r1`, `nistb283`, `sect409k1`, `nistk409`, `sect571k1`, `nistk571`, `sect571r1`, `nistb571`, `secp160k1`, `secp160r1`, `secp160r2`, `secp192k1`, `secp192r1`, `nistp192`, `secp224k1`, `secp224r1`, `nistp224`, or `prime192v1`.

`secp256r1` is considered as the default curve if this option is not specified.

`--config|-c`

Specify the name of the configuration for which you want to create the certificate.

`--server-name|-s`

Specify the host name of the server for which you are creating a self-signed certificate. This option can also be referred to as the Common Name.

`--nickname|-n`

Enter a short name for the certificate that you want to create.

Example

```
tadm create-selfsigned-cert --user=admin --port=8989 --password-file=./admin.pwd
--no-prompt
--config=www.example.org --server-name=serverhost
--nickname=cert1
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [install-cert](#), [list-certs](#), [delete-cert](#), [get-cert-prop](#), [create-cert-request](#), [set-cert-trust-prop](#)

create-tcp-listener

Syntax

```
tadm create-tcp-listener common_options [--no_enabled] [--ip=address]
[--acceptor-threads=count] [--family=name] [--listen-queue-size=size]
[--receive-buffer-size=size] [--send-buffer-size=size] [--description=text]
--listener-port=number --config=config_name --tcp-proxy=tcp_proxy_name listener_
name
```

Description

Use this command to create a new TCP listener socket. When a new request comes in, Oracle Traffic Director determines which TCP proxy to send it to, based on the configured TCP listener.

Options

For information about *common_options*, run the [help](#) command.

`--no-enabled|-n`

Specify this option to disable the TCP listener at runtime.

`--ip|-I`

Indicates the IP address of the host computer. Specify an asterisk (*) for the TCP listener to listen to all the available IP addresses on the host computer.

`--acceptor-threads|-a`

Specify the number of threads dedicated to accept the connections received by this listener. The range of values is 1 to 128.

`--family|-f`

Specify the internet protocol family, for example: IPV4, and IPV6. The default is IPV4 (`family=inet`). To use the IPV6 address, specify `family=inet6`. For Sockets Direct Protocol (SDP), specify `family=inet-sdp`.

`--listen-queue-size|-l`

Specify the size (in bytes) of the operating system listen queue back log. The range of values is 1 to 65536.

`--receive-buffer-size|-r`

Specify the size (in bytes) of the operating system socket receive buffer. The range of values is 1 to 1048576.

`--send-buffer-size|-B`

Specify the size (in bytes) of the operating system socket send buffer. The range of values is 1 to 1048576.

`--description|-D`

Enter a description for the TCP listener.

`--listener-port|-P`

Specify the port number where the configuration binds to and listens for requests. The range of values is 1 to 65535.

`--config|-c`

Specify the name of the configuration for which you want to create the new TCP listener socket.

`--tcp-proxy|-r`

Specify the name of the TCP proxy.

Operands

`listener-name`

Specify the name for the TCP listener that you want to create.

Example

```
tadm create-tcp-listener --user=admin --host=admin.example.com
--password-file=./admin.passwd --port=8989
--no-prompt --listener-port=8082 --tcp-proxy=TCP_Proxy1 --config=www.example.org
TCP_Listener1
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [delete-tcp-listener](#), [list-tcp-listeners](#), [get-tcp-listener-prop](#), [set-tcp-listener-prop](#)

create-tcp-proxy

Syntax

```
tadm create-tcp-proxy common_options
[--origin-server-pool=origin_server_pool_name] --config=config_name tcp_proxy_name
```

Description

Use this command to create a new TCP proxy. A TCP proxy handles TCP requests through TCP listeners for traffic tunnelling to the listed origin servers. A TCP proxy can have several TCP listeners associated with it.

Options

For information about *common_options*, run the [help](#) command.

--origin-server-pool | -o

Specify the name of the origin-server pool for which you want to

--config | -c

Specify the name of the configuration for which you want to create a variable.

Operands

tcp-proxy-name

The name of the TCP proxy.

Example

```
tadm create-tcp-proxy --user=admin --host=admin.example.com
--password-file=./admin.passwd --port=8989
--origin-server-pool=test-pool --config=www.example.org tcp_name1
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [delete-tcp-proxy](#), [list-tcp-proxies](#), [get-tcp-proxy-prop](#), [set-tcp-proxy-prop](#)

create-variable

Syntax

```
tadm create-variable common_options [--vs=vs_name]  
[--description=text] --config=config_name (var_name=value) +
```

Description

Use this command to create a `server.xml` variable. You can create a variable at the server as well as the virtual server levels. The variable element defines a variable for use in expressions, log formats, and `obj.conf` parameters.

Options

For information about `common_options`, run the [help](#) command.

--vs|-s

Specify the name of the virtual server for which you want to create a variable.

--description|-D

Specify the description of the `server.xml` variable that you want to create.

--config|-c

Specify the name of the configuration for which you want to create a variable.

Operands

`var-name=value`

Specify `name=value` pairs for one or more properties that you want to define. The `name=value` pairs should be separated by spaces.

Example

```
tadm create-variable --user=admin --host=admin.example.com  
--password-file=./admin.passwd --port=8989  
--no-prompt --config=www.example.org foo=bar
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [delete-variable](#), [list-variables](#)

create-virtual-server

Syntax

```
tadm create-virtual-server common_options [--http-listener=name]
[--host-pattern=pattern1,pattern2...]
[--canonical-server-name=hostname] [--log-file=path] --origin-server-pool=name
--config=config_name virtual_server_name
```

Description

Use this command to create a new virtual server. All virtual servers have an HTTP listener specified. When a new request comes in, the Oracle Traffic Director determines which virtual server to send it to, based on the configured HTTP listener.

Options

For information about *common_options*, run the [help](#) command.

`--http-listener|-r`

Specify the name of an HTTP listener associated with one or more of the virtual server's host names.

Note: The property `http-listener` enables you to specify multiple values, with each value enclosed in quotes and separated by commas. For example: `http-listener="http_listener1", "http_listener2"`

`--host-pattern|-t`

Define a list of hosts to be added to the new virtual server.

Note: The property `host-pattern` enables you to specify multiple values, with each value enclosed in quotes and separated by commas.

`--canonical-server-name|-n`

Specify a canonical host name of the virtual server. Requests that use a different host name are redirected to this host name.

`--log-file|-f`

Specifies the log file for the virtual server. The value is the log file name, for example, `../logs/errors`.

`--origin-server-pool|-o`

Specify the name of the origin-server pool for which you want to create a virtual-server.

`--config|-c`

Specify the configuration where you want to create a new virtual server.

Operands

virtual-server-name

Specify the name of the virtual server.

Example

```
tadm create-virtual-server --user=admin --host=admin.example.com
--password-file=./admin.passwd --port=8989
--no-prompt --origin-server-pool=test-pool
--config=www.example.org virtual-server-1
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [set-virtual-server-prop](#), [delete-virtual-server](#), [get-virtual-server-prop](#),
[list-virtual-servers](#), [copy-virtual-server](#)

delete-cache-rule

Syntax

```
tadm delete-cache-rule common_options --config=config_name --vs=vs_name cache_rule_name
```

Description

Use this command to delete a cache rule.

Options

For information about *common_options*, run the [help](#) command.

--config|-c

Specify the name of the configuration for which you want to delete a cache rule.

--vs|-s

Specify the virtual server.

Operands

cache-rule-name

Specify the cache rule name.

Example

```
tadm delete-cache-rule --user=admin --password-file=./admin.passwd  
--host=admin.example.com --port=8989 --no-prompt  
--config=www.example.org --vs=soa.example.org  
cache-rule-1
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-cache-rule](#), [list-cache-rules](#)

delete-cert

Syntax

```
tadm delete-cert common_options [--token=name] [--force]
--config=config_name nickname
```

Description

Use this command to delete a certificate. The `delete-cert` command prompts for a token password if the token is password protected.

Options

For information about `common_options`, run the [help](#) command.

`--token|-t`

Specify the token (cryptographic device) name, which contains the encrypted public key.

`--force|-f`

Specify this option to enable a forced deletion of a certificate.

`--config|-c`

Specify the name of the configuration for which you are deleting the certificate.

Operands

nickname

Specify the short name of the certificate that you want to delete.

Example

```
tadm delete-cert --user=admin --password-file=./admin.passwd
--host=admin.example.com --port=8989 --no-prompt
--config=www.example.org "Certificate Manager - Oracle"
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-cert-request](#), [list-certs](#), [install-cert](#), [get-cert-prop](#), [create-selfsigned-cert](#)

delete-compression-rule

Syntax

```
tadm delete-compression-rule common_options --config=config_name  
--vs=vs_name compression_rule_name
```

Description

Use this command to delete a compression rule.

Options

For information about *common_options*, run the [help](#) command.

--config|-c

Specify the configuration name for which you want to delete a compression rule.

--vs|-s

Specify the name of the virtual server.

Operands

compression-rule-name

Specify the compression rule name.

Example

```
tadm delete-compression-rule --user=admin --password-file=./admin.passwd  
--host=admin.example.com --port=8989 --no-prompt  
--config=www.example.org --vs=soa.example.org compression-rule-2
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-compression-rule](#), [get-compression-rule-prop](#), [list-compression-rules](#),
[set-compression-rule-prop](#)

delete-config

Syntax

```
tadm delete-config common_options config_name
```

Description

Use this command to delete a configuration. You can delete a configuration only if the configuration has no server instances referring to it.

Options

For information about `common_options`, run the [help](#) command.

Operands

`config-name`

Specify the name of the configuration that you want to delete.

Example

```
tadm delete-config --user=admin --host=admin.example.com  
--password-file=./admin.passwd --port=8989 --no-prompt  
config-1
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-config](#), [list-configs](#), [deploy-config](#), [copy-config](#), [pull-config](#), [set-config-file](#), [get-config-file](#), [restore-config](#)

delete-crl

Syntax

```
tadm delete-crl common_options --config=config_name issuer_name
```

Description

Use this command to delete a CRL (Certificate Revocation List).

Options

For information about *common_options*, run the [help](#) command.

`--config|-c`

Specify the name of the configuration from which the CRL is being deleted.

Operands

issuer-name

Specify the name of the CRL issuer.

Example

```
tadm delete-crl --user=admin --host=admin.example.com  
--password-file=./admin.passwd --port=8989  
--no-prompt --config=www.example.org "GlobalSign ServerSign CA"
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [install-crl](#), [list-crls](#), [get-crl-prop](#)

delete-error-page

Syntax

```
tadm delete-error-page common_options --config=config_name --vs=vs_name  
--code=error_code
```

Description

Use this command to delete a error page.

Options

For information about `common_options`, run the [help](#) command.

`--config|-c`

Specify the configuration for which you want to delete a error page.

`--vs|-s`

Specify the name of the virtual server.

`--code|-d`

Specify the error code for which you want to create an error page. Range is between 400 to 599, inclusive.

Example

```
tadm delete-error-page --user=admin --host=admin.example.com  
--password-file=./admin.passwd --port=8989  
--no-prompt --config=www.example.org --vs=soa.example.org  
--code=404
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-error-page](#), [list-error-pages](#)

delete-event

Syntax

```
tadm delete-event common_options
--config=config_name
--command=restart|reconfig|rotate-log|rotate-access-log|update-crl|commandline
(--time=hh:mm[--month=1-12]
[--day-of-week=sun|mon|tue|wed|thu|fri|sat] [--day-of-month=1-31]) |
--interval=number_of_seconds)
```

Description

Use this command to delete a scheduled event.

Options

For information about *common_options*, run the [help](#) command.

--config|-c

Specify the configuration for which you want to delete an event.

--command|-C

Specify the command that the event executes. The values can be restart, reconfig, rotate-log, rotate-access-log, update-crl, or any executable command.

--time|-t

Specify the time when you want this event to start. The time format is hh:mm, for example, 12:30.

--month|-m

Specify the month when you want this event to start. The range of values is 1 to 12.

--day-of-week|-k

Specify the day of the week when you want this event to occur. The values can be Sun, Mon, Tue, Wed, Thu, Fri or Sat.

--day-of-month|-d

Specify the day of the month when you want this event to occur. The range of values is 1 to 31.

--interval|-r

Specify the time interval at which you want this event to occur. The range of values is 60 to 86400 seconds.

Example

```
tadm delete-event --user=admin --host=admin.example.com
--password-file=./admin.passwd --port=8989
--no-prompt --config=www.example.org --command=restart
--interval=600
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-event](#), [list-events](#), [disable-event](#), [enable-event](#)

delete-failover-group

Syntax

```
tadm delete-failover-group common_options --config=config_name [--force]
--virtual-ip=VIP
```

Description

Use this command to delete a failover group. To change the VIP or any property of a failover group, you should delete the failover group and create it afresh.

When deleting a failover group, if the administration node process is running as `non-root` on the node where the instances are located and if at least one failover group is still available, then you must run `start-failover` on those nodes as a `root` user. This is to manually restart the failover. On the other hand, after deleting a failover group, if no other failover groups are available for the corresponding instances, then `stop-failover` must be executed to stop the failover. If you do not execute either `start-failover` or `stop-failover`, then the VIP associated with the deleted failover group will continue to be available.

Options

For information about `common_options`, run the [help](#) command.

`--config|-c`

Specify the configuration for which you want to delete a failover group.

`--virtual-ip|-i`

Specify the virtual IP address of the failover group that you want to delete.

`force|-f`

Specify this option to delete the failover group even if the nodes are offline.

Example

```
tadm delete-failover-group --config=soa --virtual-ip=10.228.12.250
```

```
tadm start-failover --user=admin
```

```
--password-file=./admin.passwd --host=admin.example.com --port=8989
```

```
--no-prompt --config=soa --instance-home=/home/otd
```

```
tadm stop-failover --user=admin
```

```
--password-file=./admin.passwd --host=admin.example.com --port=8989
```

```
--no-prompt --config=www.example.org --instance-home=/home/otd
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-failover-group](#), [list-failover-groups](#), [set-failover-group-primary](#),
[get-failover-group-prop](#), [start-failover](#), [stop-failover](#)

delete-http-listener

Syntax

```
tadm delete-http-listener common_options [--force] --config=config_name listener_name
```

Description

Use this command to delete an HTTP listener socket.

Options

For information about *common_options*, run the [help](#) command.

--force|-f

Specify this option to enable a forced deletion of a HTTP listener.

--config|-c

Specify the name of the configuration where the HTTP listener socket exists.

Operands

listener-name

Specify the name of the HTTP listener that you want to delete.

Example

```
tadm delete-http-listener --user=admin --host=admin.example.com
--password-file=./admin.passwd --port=8989
--no-prompt --config=www.example.org http-listener-1
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-http-listener](#), [set-http-listener-prop](#), [set-http-listener-prop](#), [list-http-listeners](#)

delete-instance

Syntax

```
tadm delete-instance common_options [--save-logs] [--force]
--config=config_name (node_host)+
```

Description

Use this command to delete instances of the specified configuration and nodes. If a specific instance is participating in failover groups, you cannot delete it.

Note: When you delete instances of a node that is service-enabled, then the corresponding services for those instances are also deleted.

Options

For information about *common_options*, run the [help](#) command.

--save-logs|-S

Specify this option to save the logs while deleting an instance.

--force|-f

Specify this option to enable a forced deletion of an instance. You can delete a instance which is participating in a failover group.

--config|-c

Specify the name of the configuration that the instance points to.

Operands

node-host

Specify the name of the node.

Example

```
tadm delete-instance --user=admin --password-file=./admin.passwd
--host=admin.example.com --port=8989 --no-prompt
--config=www.example.org serverhost
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-instance](#), [list-instances](#), [start-instance](#), [stop-instance](#), [restart-instance](#), [reconfig-instance](#), [list-nodes](#)

delete-origin-server

Syntax

```
tadm delete-origin-server common_options --config=config_name  
--origin-server-pool=origin_server_pool_name host:port
```

Description

Use this command to delete an origin server.

Options

For information about *common_options*, run the [help](#) command.

`--config|-c`

Specify the configuration for which you want to delete an origin server.

`--origin-server-pool|-o`

Specify the name of the origin-server pool for which you want to delete an origin server.

Example

```
tadm delete-origin-server --user=admin --host=admin.example.com  
--password-file=./admin.passwd --port=8989  
--no-prompt --config=www.example.org --origin-server-pool=test-pool  
www.mail.com:8080. ':'
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [delete-origin-server](#), [list-origin-servers](#), [get-origin-server-prop](#),
[set-origin-server-prop](#)

delete-origin-server-pool

Syntax

```
tadm delete-origin-server-pool common_options --config=config_name  
origin_server_pool_name
```

Description

Use this command to delete a origin-server pool.

Options

For information about `common_options`, run the [help](#) command.

`--config|-c`

Specify the configuration for which you want to delete the origin-server pool.

Operands

`origin-server-pool-name`

Specify the name of the origin-server pool to be deleted.

Example

```
tadm delete-origin-server-pool --user=admin --host=admin.example.com  
--password-file=./admin.passwd --port=8989  
--no-prompt --config=www.example.org test-pool
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [list-origin-server-pools](#), [delete-origin-server-pool](#), [get-origin-server-pool-prop](#),
[set-origin-server-pool-prop](#)

delete-request-limit

Syntax

```
tadm delete-request-limit common_options --config=config_name --vs=vs_name  
request_limit_name
```

Description

Use this command to delete the request limit.

Options

For information about *common_options*, run the [help](#) command.

--config|-c

Specify the configuration for which you want to delete the request limit.

--vs|-s

Specify the name of the virtual server for which you want to delete the request limit.

Operands

request-limit-name

Specify the name of the request limit to be deleted.

Example

```
tadm delete-request-limit --user=admin --host=admin.example.com  
--password-file=./admin.passwd --port=8989  
--no-prompt --config=www.example.org --vs=soa.example.org  
request-limit-1
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-request-limit](#), [list-request-limits](#), [get-request-limit-prop](#),
[set-request-limit-prop](#)

delete-route

Syntax

```
tadm delete-route commons_options --config=config_name --vs=vs_name route_name
```

Description

Use this command to delete the route.

Options

For information about *common_options*, run the [help](#) command.

`--config|-c`

Specify the configuration for which you want to delete the route.

`--vs|-s`

Specify the name of the virtual server for which you want to delete the route.

Operands

route-name

Specify the route name.

Example

```
tadm delete-route --user=admin --host=admin.example.com  
--password-file=./admin.passwd --port=8989  
--no-prompt --config=www.example.org --vs=soa.example.org  
route-5
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-route](#), [list-routes](#), [get-route-prop](#), [set-route-prop](#)

delete-tcp-listener

Syntax

```
tadm delete-tcp-listener common_options --config=config_name listener_name
```

Description

Use this command to delete a TCP listener socket.

Options

For information about *common_options*, run the [help](#) command.

--config|-c

Specify the configuration for which you want to delete a variable.

Operands

listener-name

Specify the name of the TCP listener that you want to delete.

Example

```
tadm delete-tcp-listener --user=admin --host=admin.example.com  
--password-file=./admin.passwd --port=8989  
--no-prompt --config=www.example.org TCP_Listener1
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-tcp-listener](#), [list-tcp-listeners](#), [get-tcp-listener-prop](#), [set-tcp-listener-prop](#)

delete-tcp-proxy

Syntax

```
tadm delete-tcp-proxy common_options --config=config_name tcp_proxy_name
```

Description

Use this command to delete a TCP proxy.

Options

For information about *common_options*, run the [help](#) command.

`--config|-c`

Specify the configuration for which you want to delete a variable.

Operands

tcp-proxy-name

Specify the name of the proxy that you want to delete.

Example

```
tadm delete-tcp-proxy --user=admin --host=admin.example.com  
--password-file=./admin.passwd --port=8989  
--no-prompt --config=www.example.org tcp_proxy1
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-tcp-proxy](#), [list-tcp-proxies](#), [get-tcp-proxy-prop](#), [set-tcp-proxy-prop](#)

delete-variable

Syntax

```
tadm delete-variable common_options [--vs=vs_name] --config=config_name (var_name) +
```

Description

Use this command to delete a `server.xml` variable.

Options

For information about `common_options`, run the [help](#) command.

--vs|-s

Specify the name of the virtual server for which you want to delete a variable.

--config|-c

Specify the configuration for which you want to delete a variable.

Operands

var-name

Specify the name of the variable that you want to delete.

Example

```
tadm delete-variable --user=admin --host=admin.example.com  
--password-file=./admin.passwd --port=8989  
--no-prompt --vs=soa.example.org --config=www.example.org foo
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-variable](#), [list-variables](#)

delete-virtual-server

Syntax

```
tadm delete-virtual-server common_options --config=config_name  
virtual_server_name
```

Description

Use this command to delete a virtual server.

Options

For information about *common_options*, run the [help](#) command.

--config|-c

Specify the configuration for which you want to delete a virtual server.

Operands

virtual-server-name

Specify the name of the virtual server that you want to delete.

Example

```
tadm delete-virtual-server --user=admin --host=admin.example.com  
--password-file=./admin.passwd --port=8989  
--no-prompt --config=www.example.org virtual-server-1
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-virtual-server](#), [set-virtual-server-prop](#), [get-virtual-server-prop](#),
[list-virtual-servers](#), [copy-virtual-server](#)

delete-webapp-firewall-ruleset

Syntax

```
tadm delete-webapp-firewall-ruleset common_options --config=config_name [--vs=vs_name] ruleset_file_name
```

Description

Use this command to delete a ruleset file for a web application firewall.

Options

For information about *common_options*, run the [help](#) command.

--config|-c

Specify the configuration for which you want to delete a web application firewall ruleset.

--vs|-s

Specify the name of the virtual server.

Operands

ruleset-file-name

Specify the name of the ruleset file that needs to be deleted.

Example

```
tadm delete-webapp-firewall-ruleset --user=admin --host=admin.example.com  
--password-file=./admin.passwd --port=8989  
--no-prompt --config=www.example.org --vs=soa.example.org waf-rule.conf
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [install-webapp-firewall-ruleset](#), [list-webapp-firewall-rulesets](#)

deploy-config

Syntax

```
tadm deploy-config common_options [--force] [--restart] [--no-reconfig] config_name
```

Description

Use this command to deploy a configuration to the nodes. Whenever you create a new configuration or make changes to an existing configuration, you must deploy the configuration for the changes to take effect. The configuration is deployed to all the instances of a configuration.

Options

For information about *common_options*, run the [help](#) command.

`--force|-f`

Specify this option for the command to overwrite any manual changes done to the configuration files in the instance. By using this option, the instance is overwritten with the latest version of all the files in the config-store.

`--restart|-r`

Specify this option for the command to restart the instances running in this configuration.

`--no-reconfig|-o`

If you specify this option, the command does not reconfigure the running server instances of this configuration.

Operands

config-name

Specify the name of the configuration that you want to deploy.

Example

```
tadm deploy-config --user=admin --password-file=./admin.passwd  
--host=admin.example.com --port=8989 --no-prompt configuration-1
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-config](#), [list-configs](#), [delete-config](#), [copy-config](#), [pull-config](#), [restore-config](#), [list-config-files](#), [get-config-file](#), [set-config-file](#)

disable-access-log

Syntax

```
tadm disable-access-log common_options --config=config_name  
[--vs=vs_name]
```

Description

Use this command to disable the access-log.

Options

For information about *common_options*, run the [help](#) command.

--config|-c

Specify the name of the configuration for disabling the access-log.

--vs|-s

Specify the name of the virtual server.

Example

```
tadm disable-access-log --user=admin --host=admin.example.com  
--password-file=./admin.passwd --port=8989  
--no-prompt --config=www.example.org
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [get-access-log-prop](#), [enable-access-log](#)

disable-admin-ldap-auth

Syntax

```
tadm disable-admin-ldap-auth common_options
```

Description

Use this command to disable the administration server from authenticating against a Lightweight Directory Access Protocol (LDAP) server. The administration server would use the default keyfile for authentication instead of LDAP.

Options

For information about *common_options*, run the [help](#) command.

Example

```
tadm disable-admin-ldap-auth --user=admin --host=admin.example.com  
--password-file=./admin.passwd --port=8989  
--no-prompt
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [enable-admin-ldap-auth](#), [get-admin-ldap-auth-prop](#), [renew-admin-certs](#),
[reset-admin-password](#)

disable-ciphers

Syntax

```
tadm disable-ciphers common_options --config=config_name  
(--http-listener=name|--tcp-listener=name) (ssl3tls_cipher_name) +
```

Description

Use this command to disable Secure Sockets Layer (SSL) ciphers.

Options

For information about *common_options*, run the [help](#) command.

--config|-c

Specify the name of the configuration file that contains the metadata to configure the runtime services of Oracle Traffic Director.

--http-listener|-r

Specify the name of the HTTP listener.

--tcp-listener|-t

Specify the name of the TCP listener.

Operands

ssl3tls_cipher_name

Specify the name of the ssl3tls cipher that you want to disable.

Example

```
tadm disable-ciphers --user=admin --host=admin.example.com  
--password-file=./admin.passwd --port=8989  
--no-prompt --config=www.example.org --http-listener=www.example.org_ls  
cipher-1
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [enable-ciphers](#), [list-ciphers](#)

disable-event

Syntax

```
tadm disable-event common_options [ (--time=hh:mm [--month=1-12]
[--day-of-week=sun|mon|tue|wed|thu|fri|sat]
[--day-of-month=1-31]) | --interval=number_of_seconds ]
--config=config_name
--command=restart|reconfig|rotate-log|rotate-access-log|update-crl|commandline
```

Description

Use this command to disable a scheduled event.

Options

For information about *common_options*, run the [help](#) command.

--time|-t

Specify the time when you want this event to start. The time format is hh:mm, (for example, 12:30).

--month|-m

Specify the month when you want this event to occur. The range of values is 1 to 12.

--day-of-week|-k

Specify the day of the week when you want this event to occur. The values can be Sun, Mon, Tue, Wed, Thu, Fri, or Sat.

--day-of-month|-d

Specify the day of the month when you want this event to occur. The range of values is 1 to 31.

--interval|-r

Specify the time interval at which you want this event to occur. The range of values is 60 to 86400 seconds.

--config|-c

Specify the name of the configuration for disabling the event.

--command|-C

Specify the command that the event executes. The value can be restart, reconfig, rotate-log, rotate-access-log, update-crl, or any executable command.

Example

```
tadm disable-event --user=admin --host=admin.example.com
--password-file=./admin.passwd --port=8989
--no-prompt --interval=3600 --config=www.example.org
--command=restart
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-event](#), [delete-event](#), [list-events](#), [enable-event](#)

disable-perfdump

Syntax

```
tadm disable-perfdump common_options --config=config_name --vs=vs_name
```

Description

Use this command to disable perfdump.

Options

For information about *common_options*, run the [help](#) command.

`--config|-c`

Specify the configuration for which you want to disable perfdump.

`--vs|-s`

Specify the name of the virtual server for which you want to disable perfdump.

Example

```
tadm disable-perfdump --user=admin --host=admin.example.com  
--password-file=./admin.passwd --port=8989  
--no-prompt --config=www.example.org --vs=soa.example.org
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [enable-perfdump](#), [get-perfdump-prop](#)

disable-route-auth

Syntax

```
tadm disable-route-auth common_options --config=config_name  
--vs=vs_name --route=route_name
```

Description

Use this command to disable the route authentication.

Options

For information about *common_options*, run the [help](#) command.

--config|-c

Specify the configuration for which you want to disable route authentication.

--vs|-s

Specify the virtual server.

--route|-r

Specify the route name.

Example

```
tadm disable-route-auth --user=admin --password-file=./admin.passwd  
--host=admin.example.com --port=8989 --no-prompt  
--config=www.example.org --vs=soa.example.org --route=Route-2
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [enable-route-auth](#)

disable-services

Syntax

```
tadm disable-services common_options  
(node_host)*
```

Description

Use this command to remove services for all the instances on a specified node.

Note: The `disable-services` command will fail if the administration server is not running as a privileged user.

Operands

`node-host`

Specify the name of the node.

Example

```
tadm disable-services --user=admin --password-file=./admin.passwd  
--host=admin.example.com --port=8989 --no-prompt  
serverhost
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [enable-services](#)

disable-stats-xml

Syntax

```
tadm disable-stats-xml common_options --config=config_name  
--vs=vs_name
```

Description

Use this command to disable the server instance statistics.

Options

For information about *common_options*, run the [help](#) command.

--config|-c

Specify the name of the configuration for which you want to disable the server instance statistics.

--vs|-s

Specify the name of the virtual server.

Example

```
tadm disable-stats-xml --user=admin --password-file=./admin.passwd  
--host=admin.example.com --port=8989 --no-prompt  
--config=www.example.org --vs=soa.example.org
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [get-stats-xml](#), [get-stats-xml-prop](#), [enable-stats-xml](#)

disable-tcp-access-log

Syntax

```
tadm disable-tcp-access-log common_options --config=config_name
```

Description

Use this command to disable the TCP access log for a configuration.

Options

For information about *common_options*, run the [help](#) command.

`--config|-c`

Specify the name of the configuration for which you want to disable TCP access log.

Example

```
tadm disable-tcp-access-log --user=admin --password-file=./admin.passwd  
--host=admin.example.com --port=8989 --no-prompt  
--config=www.example.org
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [enable-tcp-access-log](#), [get-tcp-access-log](#), [get-tcp-thread-pool-prop](#)

disable-webapp-firewall

Syntax

```
tadm disable-webapp-firewall common_options --config=config_name  
--vs=vs_name
```

Description

Use this command to disable the web application firewall for a specific virtual server.

Options

For information about *common_options*, run the [help](#) command.

--config|-c

Specify the name of the configuration for which you want to disable the web application firewall.

--vs|-s

Specify the name of the virtual server.

Example

```
tadm disable-webapp-firewall --user=admin --password-file=./admin.passwd  
--host=admin.example.com --port=8989 --no-prompt  
--config=www.example.org --vs=soa.example.org
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [enable-webapp-firewall](#), [get-webapp-firewall-prop](#)

enable-access-log

Syntax

```
tadm enable-access-log common_options [--log-ip]
[--format=log_format] --config=config_name [--vs=vs_name]
--file=log_file
```

Description

Use this command to enable the access-log.

Options

For information about `common_options`, run the [help](#) command.

`--log-ip|-o`

Set this option to `true` to log the IP of the client into the access log.

`--format|-f`

Specify the log format string for an access log.

`--config|-c`

Specify the name of the configuration for enabling the access-log.

`--vs|-s`

Specify the name of the virtual server.

`--file|-l`

Specify the file name for the access log.

Example

```
tadm enable-access-log --user=admin --host=admin.example.com
--password-file=./admin.passwd --port=8989
--no-prompt --config=www.example.org --vs=soa.example.org
--file=./logs/access.log
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [get-access-log-prop](#), [disable-access-log](#)

enable-admin-ldap-auth

Syntax

```
tadm enable-admin-ldap-auth common_options [--group-search-filter=filter]
[--search-filter=filter] [--dc-suffix=suffix]
[--group-search-attr=attribute] [--bind-dn=bind_dn]
[--auth-expiring-url=url] [--timeout=timeout]
--ldap-url=ldap://server:port/dc=acme,dc=com --allow-group=(comma separated list
of valid group names)
```

Description

Use this command to enable the administration server to authenticate against a Lightweight Directory Access Protocol (LDAP) server.

Options

For information about *common_options*, run the [help](#) command.

`--group-search-filter | -o`

Specify the search filter to find group memberships for the user. Default value: `uniquemember`.

`--search-filter | -f`

Specify the search filter to find a user. Default value: `uid`. You can use the search options to interoperate with Microsoft Active Directory (MSAD). By default, MSAD does not store the user IDs in the usual `uid` attribute. Instead, it stores the user IDs in an attribute called `samAccountName`. Therefore, when LDAP searches a MSAD directory to find a user, it does not find a match because it attempts to match the `uid` attribute. In Oracle Traffic Director, you can set the `--search-filter` option to override the MSAD default attribute.

`--dc-suffix | -x`

Specify a suffix for the LDAP database. This parameter defines the root of the Domain Component (dc) tree and is relative to the base DN in the LDAP URL.

`--group-search-attr | -t`

Specify the LDAP attribute name that contains group name entries. Default value: `CN`.

`--bind-dn | -d`

Specify the name that the administration server uses to initially bind or log in to the directory server, for example, `cn=Directory Manager`. Binding determines the permission level that you are granted for the duration of a connection. The DN supplied in a bind request can be the DN of an alias entry.

`--auth-expiring-url | -a`

Specify the URL to which the server redirects the request if the password is going to expire soon.

`--time-out | -m`

Specify the time out option for the LDAP authentication.

`--ldap-url | -l`

Specify the URL of the LDAP authentication database. The type of authentication database is specified in the URL scheme. The URL format is:

```
ldap://ldaphost:port/<base-dn>
```

`--allow-group|-g`

Specify a comma separated list of groups. Users belonging to these groups are allowed to login.

Example

```
tadm enable-admin-ldap-auth --user=admin --host=admin.example.com
--password-file=./admin.passwd --port=8989
--no-prompt
rcfile=null --ldap-url=ldap://serverhost.com:3950/dc=xyz,dc=xyz,dc=xyz
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [disable-admin-ldap-auth](#), [get-admin-ldap-auth-prop](#)

enable-ciphers

Syntax

```
tadm enable-ciphers common_options --config=config_name
(--http-listener=name|--tcp-listener=name) (ssl3tls_cipher_name) +
```

Description

Use this command to enable the Secure Sockets Layer (SSL) ciphers. A cipher is a cryptographic algorithm that is used for encryption or decryption.

Options

For information about *common_options*, run the [help](#) command.

--config|-c

Specify the name of the configuration file that contains the metadata to configure the runtime services of Oracle Traffic Director.

--http-listener|-r

Specify the name of the HTTP listener.

--tcp-listener|-t

Specify the name of the TCP listener.

Operands

ssl3tls-cipher-name

Specify the name of the ssl3tls cipher. For a list of ciphers, see the [list-ciphers](#) help page.

Example

```
tadm enable-ciphers --user=admin --password-file=./admin.passwd
--host=admin.example.com --port=8989 --no-prompt
--config=www.example.org --http-listener=config1_ls
SSL_RSA_EXPORT_WITH_RC4_40_MD5
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [disable-ciphers](#), [list-ciphers](#)

enable-event

Syntax

```
tadm enable-event common_options [--time=hh:mm [--month=1-12]
[--day-of-week=sun|mon|tue|wed|thu|fri|sat]
[--day-of-month=1-31]] | --interval=number_of_seconds ] --config=config_name
--command=restart|reconfig|rotate-log|rotate-access-log|update-crl|commandline
```

For more information about the syntax notations, run the [help](#) command.

Description

Use this command to enable an event that you have created.

Options

For information about *common_options*, run the [help](#) command.

`--time|-t`

Specify the time when you want this event to start. The time format is hh:mm, for example, 12:30.

`--month|-m`

Specify the month when you want this event to occur. The range of values is 1 to 12.

`--day-of-week|-k`

Specify the day of the week when you want this event to occur. The values can be Sun, Mon, Tue, Wed, Thu, Fri, or Sat.

`--day-of-month|-d`

Specify the day of the month when you want this event to occur. The range of values is 1 to 31.

`--interval|-r`

Specify the time interval at which you want this event to occur. The range of values is 60 to 86400 seconds.

`--config|-c`

Specify the configuration for which you want to enable an event.

`--command|-C`

Specify the command the event executes. The value can be `restart`, `reconfig`, `rotate-log`, `rotate-access-log`, `update-crl`, or any executable command.

Example

```
tadm enable-event --user=admin --password-file=./admin.passwd
--host=admin.example.com --port=8989 --no-prompt --time=20:30 --month=11
--day-of-week=mon --day-of-month=15 --config=www.example.org
--command=restart
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-event](#), [delete-event](#), [list-events](#), [disable-event](#)

enable-perfdump

Syntax

```
tadm enable-perfdump common_options [--uri=uri] --config=config_name --vs=vs_name
```

Description

Use this command to enable the `perfdump` utility. Perfdump is a Server Application Function (SAF) built into Oracle Traffic Director that collects various pieces of performance data from the OTD internal statistics and displays them in ASCII text. The `perfdump` output does not display all the statistics available through the command-line statistics or the Administrator Console.

You can use `perfdump` even if the Administration Server is not running. You can view the `perfdump` output through the CLI, which is enabled by default, or you can view the `perfdump` output through a URI, which you have to enable. If you enable the URI, you must control access to the `perfdump` URI, else it is visible to users. With `perfdump`, the statistics are unified. Rather than monitoring a single process, statistics are multiplied by the number of processes, which provides you with an accurate view of the server as a whole.

Options

For information about `common_options`, run the [help](#) command.

`--uri|-r`

Specify the URI at which the `perfdump` report should be available.

`--config|-c`

Specify the name of the configuration to enable `perfdump`.

`--vs|-s`

Specify the name of the virtual server for which you want to enable `perfdump`.

Example

```
tadm enable-perfdump --user=admin --password-file=./admin.passwd  
--host=admin.example.com --port=8989 --no-prompt  
--config=www.example.org --vs=soa.example.org
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [get-perfdump](#), [get-perfdump-prop](#), [disable-perfdump](#)

enable-route-auth

Syntax

```
tadm enable-route-auth common_options --config=config_name
--vs=vs_name --route=route_name ((--client-cert-nickname=nick_name) |
(--auth-user=user --auth-header=auth_header))
```

Description

Use this command to enable the route authentication. Specify the client-cert-nickname to enable the client authentication. Specify the auth-user to enable the basic authentication.

Options

For information about *common_options*, run the [help](#) command.

--config|-c

Specify the configuration for which you want to enable route authentication.

--vs|-s

Specify the virtual server.

--route|-r

Specify the route name.

--client-cert-nickname|-l

Specify the client certificate nickname.

--auth-user|-t

Specify the authenticated user.

--auth-header|-d

Specify the name of the authentication header.

Example

```
tadm enable-route-auth --user=admin --password-file=./admin.passwd
--host=admin.example.com --port=8989 --no-prompt
--config=www.example.org --vs=soa.example.org
--route=Route1 --auth-user=admin --auth-header=header-1-auth
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [disable-admin-ldap-auth](#), [get-admin-ldap-auth-prop](#), [disable-route-auth](#)

enable-services

Syntax

```
tadm enable-services common_options  
(node_host)*
```

Description

Use this command to create services for all instances on a specified node. The service will not be created if an existing service is found on an instance.

Note: The enable-services command will fail if the administration server is not running as a privileged user.

Operands

node-host

Specify the name of the node.

Example

```
tadm enable-services --user=admin --password-file=./admin.passwd  
--host=admin.example.com --port=8989 --no-prompt  
serverhost
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [disable-services](#)

enable-stats-xml

Syntax

```
tadm enable-stats-xml common_options [--uri=uri] --config=config_name --vs=vs_name
```

Description

Use this command to enable access to virtual-server statistics in XML format through a URI.

Options

For information about *common_options*, run the [help](#) command.

--uri|-r

Specify the URI at which the statistics report in XML format should be available.

--config|-c

Specify the configuration for which you want to enable the server instance statistics.

--vs|-s

Specify the name of the virtual server for which you want to enable the server instance statistics.

Example

```
tadm enable-stats-xml --user=admin --password-file=./admin.passwd
--host=admin.example.com --port=8989 --no-prompt
--config=www.example.org --vs=soa.example.org
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [get-stats-xml](#), [get-stats-xml-prop](#), [disable-stats-xml](#)

enable-tcp-access-log

Syntax

```
tadm enable-tcp-access-log common_options --config=config_name (--file=log_file)
```

Description

Use this command to enable TCP access log for a configuration.

Options

For information about *common_options*, run the [help](#) command.

`--config|-c`

Specify the configuration for which you want to enable TCP access log.

`--file|-l`

Specify the file name for the access log.

Example

```
tadm enable-tcp-access-log --user=admin --password-file=./admin.passwd  
--host=admin.example.com --port=8989 --no-prompt  
--config=www.example.org --file=./logs/file1.log
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [disable-tcp-access-log](#), [get-tcp-access-log-prop](#), [get-tcp-access-log](#)

enable-webapp-firewall

Syntax

```
tadm enable-webapp-firewall common_options --config=config_name --vs=vs_name
```

Description

Use this command to enable the web application firewall for a specific virtual server.

Options

For information about *common_options*, run the [help](#) command.

--config|-c

Specify the configuration for which you want to enable the web application firewall.

--vs|-s

Specify the name of the virtual server for which you want to enable the web application firewall.

Example

```
tadm enable-webapp-firewall --user=admin --password-file=./admin.passwd  
--host=admin.example.com --port=8989 --no-prompt  
--config=www.example.org --vs=soa.example.org
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [disable-webapp-firewall](#) [get-webapp-firewall-prop](#)

forward-proxy-info

Syntax

```
tadm forward-proxy-info common_options [--header=header] --config=config_name  
--vs=vs_name --route=route_name (param)
```

Description

Use this command to forward the proxy information.

Options

For information about `common_options`, run the [help](#) command.

Specify the name of the proxy parameter you want to forward.

--header|-H

Specify the name of the header.

--config|-c

Specify the configuration for which you want to forward the proxy header.

--vs|-s

Specify the name of the virtual server.

--route|-r

Specify the route name to forward the proxy header.

Operands

jroute

via

ip

cipher

proxy-agent

proxy-auth

keysize

secret-keysize

ssl-id

issuer-dn

user-dn

auth-cert

xforwarded-for

cache-info

ssl

Example

```
tadm forward-proxy-info --user=admin --host=admin.example.com
```

```
--password-file=./admin.passwd --port=8989  
--no-prompt --config=www.example.org --vs=soa.example.org  
--route=forwardproxy1 jroute
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [list-proxy-info](#), [block-proxy-info](#)

get-access-log

Syntax

```
tadm get-access-log common_options [--start-date=MM/dd/yyyy:HH:mm:ss]
[--end-date=MM/dd/yyyy:HH:mm:ss]
[--status-code=status_code] [--num-records=number_of_records] [--vs=vs_name]
--config=config_name (node_host)
```

Description

Use this command to view the Oracle Traffic Director access-log entries. The access log records information about requests to and responses from the server. If non-mandatory options are chosen, this command shows the last 100 entries of the default access log file for the selected configuration and node.

Options

For information about *common_options*, run the [help](#) command.

`--start-date|-S`

Specify the starting date and time from which the log messages must be shown. The start date should be in the dd/MM/yyyy:HH:mm:ss format.

`--end-date|-E`

Specify the ending date and time until which the log messages must be shown. The end date should be in the dd/MM/yyyy:HH:mm:ss format.

`--status-code|-o`

Specify the status code of HTTP response code, for example, 200, 300, or 400.

`--num-records|-n`

Specify the number of log messages to be shown.

`--vs|-s`

Specify the name of the virtual server. Use this option if you want to view the access file entries of a particular virtual server.

`--config|-c`

Specify the name of the configuration for which you want to view the access log information.

Operands

node-host

Specify the name of the node.

Example

```
tadm get-access-log --user=admin --host=admin.example.com
--password-file=./admin.passwd --port=8989
--no-prompt --config=www.example.org serverhost
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [get-log](#), [get-access-log-buffer-prop](#), [enable-access-log](#), [disable-access-log](#), [get-log](#), [get-log-prop](#), [set-log-prop](#), [rotate-log](#)

get-access-log-buffer-prop

Syntax

```
tadm get-access-log-buffer-prop common_options --config=config_name (property_name)*
```

Description

Use this command to view the access-log buffer properties.

Options

For information about `common_options`, run the [help](#) command.

`--config|-c`

Specify the name of the configuration for which you want to view the properties of access-log buffer.

Operands

`property-name`

Specify the name of the property that you want to view (Optional).

You can view the following access-log buffer properties:

```
enabled
buffer-size
direct-io
max-buffers
max-buffers-per-file
max-age
```

Note: The property `max-buffers-per-file` can return default as a value. Default implies that the server will compute the value of this property at runtime.

Example

```
tadm get-access-log-buffer-prop --user=admin --password-file=./admin.passwd
--host=admin.example.com --port=8989 --no-prompt
--config=www.example.org buffer-size
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [set-access-log-buffer-prop](#), [enable-access-log](#), [disable-access-log](#), [get-access-log](#), [get-log](#), [get-log-prop](#), [set-log-prop](#), [rotate-log](#)

get-access-log-prop

Syntax

```
tadm get-access-log-prop common_options --config=config_name
[--vs=vs_name] (property_name)*
```

Description

Use this command to view access-log properties.

Options

For information about *common_options*, run the [help](#) command.

--config | -c

Specify the configuration for which you want to view the access-log properties.

--vs | -s

Specify the name of virtual server.

Operands

property-name

Specify the name of the property that you want to view (Optional).

You can view the following access-log properties:

```
enabled
file
format
mode
```

Example

```
tadm get-access-log-prop --user=admin --host=admin.example.com
--password-file=./admin.passwd --port=8989
--no-prompt --config=www.example.org file
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [enable-access-log](#), [disable-access-log](#), [get-access-log](#), [get-log](#), [get-log-prop](#), [set-log-prop](#), [rotate-log](#)

get-admin-ldap-auth-prop

Syntax

```
tadm get-admin-ldap-auth-prop common_options (property_name)*
```

Description

Use this command to view the properties of Lightweight Directory Access Protocol (LDAP) authentication database, which is configured as the authentication database of the administration server.

Options

For information about `common_options`, run the [help](#) command.

Operands

`property-name`

Specify the name of the property that you want to view (Optional).

An LDAP authentication database property that you can view:

`enabled`

Example

```
tadm get-admin-ldap-auth-prop --user=admin --host=admin.example.com
--password-file=./admin.passwd --port=8989
--no-prompt enabled
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [enable-admin-ldap-auth](#), [disable-admin-ldap-auth](#)

get-admin-prop

Syntax

```
tadm get-admin-prop common_options [--node=node_name] (property_name)*
```

Description

Use this command to view the administration node properties.

Options

For information about *common_options*, run the [help](#) command.

--node|-n

Specify the name of the node.

You can view the following administration properties:

Operands

property-name

Specify the name of the property that you want to view (Optional).

You can view the following administration properties:

```
install-root
instance-home
java-home
admin-node
server-version
admin-user
server-user
ssl-port
non-ssl-port
log-file
log-level
access-log-file
host
description
admin-password
bind-ip
service-enabled
service-name
```

Example

```
tadm get-admin-prop --user=admin --host=admin.example.com
--password-file=./admin.passwd --port=8989
--no-prompt server-user
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [list-nodes](#), [set-admin-prop](#), [restart-admin](#), [stop-admin](#), [remove-node](#)

get-cache-prop

Syntax

```
tadm get-cache-prop common_options --config=config_name (property_name)*
```

Description

Use this command to view the cache properties.

Options

For information about *common_options*, run the [help](#) command.

--config|-c

Specify the name of the configuration for viewing the cache properties.

Operands

property-name

Specify the name of the property that you want to view (Optional).

You can view the following cache properties:

```
enabled  
max-entries  
replacement  
max-heap-object-size  
max-heap-space
```

Example

```
tadm get-cache-prop --user=admin --host=admin.example.com  
--password-file=certdb.newpasswd --port=8989  
--prompt=false --config=www.example.org max-entries
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [set-cache-prop](#)

get-cache-rule-prop

Syntax

```
tadm get-cache-rule-prop common_options --config=config_name --vs=vs_name  
--rule=cache_rule_name (property_name)*
```

Description

Use this command to view the cache rule properties.

Options

For information about `common_options`, run the [help](#) command.

`--config|-c`

Specify the name of the configuration for which you want to view cache rule properties.

`--vs|-s`

Specify the virtual server.

`--rule|-r`

Specify the cache rule name.

Operands

`property-name`

Specify the name of the property that you want to view (Optional).

You can view the following cache rule properties:

```
enabled  
max-reload-interval  
min-reload-interval  
last-modified-factor  
min-object-size  
max-object-size  
cache-auth  
query-maxlen  
compression  
cache-https-response  
condition
```

Example

```
tadm get-cache-rule-prop --config=www.example.org --vs=www.example.org  
--rule=cache-rule-1 query-maxlen
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [set-cache-prop](#), [set-cache-rule-prop](#)

get-cert-prop

Syntax

```
tadm get-cert-prop common_options [--token=name] --config=config_name  
--nickname=nick_name (property_name)*
```

Description

Use this command to view the certificate properties. The `get-cert-prop` command prompts for a token password if the token is password protected.

Options

For information about `common_options`, run the [help](#) command.

`--token|-t`

Specify the token or cryptographic device, which contains the encrypted public key.

`--config|-c`

Specify the name of the configuration for which the certificate properties are displayed.

`--nickname|-n`

Specify the short name or nickname of the certificate.

Operands

property-name

Specify the name of the property that you want to view (Optional).

You can view the following certificate properties:

```
Nickname  
Subject  
Issuer  
Valid From  
Valid Till  
Fingerprint  
Serial Number  
Trusted to sign Client Certificates  
Trusted to sign Server Certificates
```

Example

```
tadm get-cert-prop --user=admin --host=admin.example.com  
--password-file=./admin.passwd --port=8989  
--no-prompt --config=www.example.org --token=internal  
--nickname=OTD Trusted to sign client certificates
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [install-cert](#), [delete-cert](#), [list-certs](#), [set-cert-trust-prop](#), [create-selfsigned-cert](#),
[create-cert-request](#)

get-compression-rule-prop

Syntax

```
get-compression-rule-prop --config=config_name --vs=vs_name --rule=compression_  
rule_name (property_name)*
```

Description

Use this command to view compression rule properties.

Options

For information about `common_options`, run the [help](#) command.

`--config|-c`

Specify the configuration name for which you want to view compression rule properties.

`--vs|-s`

Specify the name of the virtual server.

`--rule|-r`

Specify the compression rule name.

Operand

`property-name`

Specify the property name that you want to view (Optional).

You can view the following compression rule properties:

`insert-vary-header`

`compression-level`

`fragment-size`

`condition`

Note: The property `compression-level` can return default as a value. Default implies that the server will compute the value of this property at runtime.

Example

```
tadm get-compression-rule-prop --config=www.example.org  
--vs=soa.example.org --rule=compression2  
compression-level
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-compression-rule](#), [delete-compression-rule](#), [list-compression-rules](#),
[set-compression-rule-prop](#)

get-config-file

Syntax

```
tadm get-config-file common_options --config=config_name (file_name)
```

Description

Use this command to view any configuration file present in the `config` directory under `server-root`.

Options

For information about `common_options`, run the [help](#) command.

`--config|-c`

Specify the name of the configuration to view the configuration file.

Operands

`file-name`

Specify the name of the configuration file that you want to view.

Example

```
tadm get-config-file --user=admin --host=admin.example.com  
--password-file=./admin.passwd --port=8989  
--no-prompt --config=www.example.org obj.conf
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-config](#), [list-configs](#), [deploy-config](#), [copy-config](#), [pull-config](#), [set-config-file](#), [delete-config](#), [list-backups](#), [restore-config](#)

get-config-prop

Syntax

```
tadm get-config-prop common_options --config=config_name  
(property_name)*
```

Description

Use this command to view the configuration properties.

Options

For information about *common_options*, run the [help](#) command.

`--config|-c`

Specify the name of the configuration for viewing the configuration file properties.

Operands

property-name

Specify the name of the property that you want to view (Optional).

You can view the following configuration properties:

user

temp-path

Example

```
tadm get-config-prop --user=admin --host=admin.example.com  
--password-file=./admin.passwd --port=8989  
--no-prompt --config=www.example.org temp-path
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [set-config-prop](#)

get-config-stats

Syntax

```
tadm get-config-stats common_options [--node=node_name]  
--config=config_name
```

Description

Use this command to view the configuration statistics at the instance or configuration level.

Options

For information about `common_options`, run the [help](#) command.

--node|-n

Specify the node name.

--config|-c

Specify the configuration for which you want to view the configuration statistics.

Example

```
tadm get-config-stats --user=admin --password-file=./admin.passwd  
--host=admin.example.com --port=8989 --no-prompt  
--config=www.example.org
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [list-nodes](#)

get-crl-prop

Syntax

```
tadm get-crl-prop common_options --config=config_name  
--issuer-name=ca_name (property_name)*
```

Description

Use this command to display the Certificate Revocation List (CRL) properties.

Options

For information about *common_options*, run the [help](#) command.

--config|-c

Specify the configuration for which you want to view the CRL properties.

--issuer-name|-r

Specify the name of the Certificate Authority (CA) issuer. The value can be the name of a company, organization, or department.

Operands

property-name

Specify the name of the property that you want to view (Optional).

You can view the following CRL properties:

crl-name

issuer

last-update

next-update

Example

```
tadm get-crl-prop --user=admin --password-file=./admin.passwd  
--host=admin.example.com --port=8989 --no-prompt --config=www.example.org  
--issuer-name="GlobalSign ServerSign CA" next-update
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [install-crl](#), [delete-crl](#), [list-crls](#)

get-dns-cache-prop

Syntax

```
tadm get-dns-cache-prop common_options --config=config_name  
(property_name)*
```

Description

Use this command to view the Domain Name Server (DNS) cache properties.

Options

For information about `common_options`, run the [help](#) command.

`--config|-c`

Specify the name of the configuration to view the DNS cache properties.

Operands

`property-name`

Specify the name of the property that you want to view (Optional).

You can view the following DNS cache properties:

`enabled`

`max-age`

`max-entries`

Example

```
tadm get-dns-cache-prop --user=admin --host=admin.example.com  
--password-file=./admin.passwd --port=8989  
--no-prompt --config=www.example.org max-age
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [set-dns-cache-prop](#)

get-dns-prop

Syntax

```
tadm get-dns-prop common_options --config=config_name (property_name)*
```

Description

Use this command to view the Domain Name Server (DNS) properties. DNS associates a standard IP address such as, 192.0.3.11, with host names such as, www.example.com.

Options

For information about *common_options*, run the [help](#) command.

--config|-c

Specify the name of the configuration to view the DNS properties.

Operands

property-name

Specify the name of the property that you want to view (Optional).

You can view the following DNS properties:

enabled

async

timeout

Example

```
tadm get-dns-prop --user=admin --host=admin.example.com  
--password-file=./admin.passwd --port=8989  
--no-prompt --config=www.example.org timeout
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [set-dns-prop](#)

get-failover-group-prop

Syntax

```
tadm get-failover-group-prop common_options --config=config_name --virtual-ip=VIP  
(property_name)*
```

Description

Use this command to view the properties of a failover group.

Options

For information about `common_options`, run the [help](#) command.

`--config|-c`

Specify the name of the configuration for which you want to view the failover group properties.

`--virtual-ip|-i`

Specify the IP address of the failover group for which you want to view properties.

Operand

`property-name`

Specify the name of the property that you want to view (Optional).

You can view the following failover group properties:

```
virtual-ip  
backup-node  
network-prefix-length  
router-id  
primary-node  
primary-nic
```

Example

```
tadm get-failover-group-prop --config=soa --virtual-ip=10.229.231.254
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [delete-failover-group](#), [create-failover-group](#), [list-failover-groups](#),
[set-failover-group-primary](#)

get-health-check-prop

Syntax

```
tadm get-health-check-prop common_options --config=config_name
--origin-server-pool=origin_server_pool_name (property_name)*
```

Description

Use this command to view the health-check properties.

Options

For information about *common_options*, run the [help](#) command.

--config|-c

Specify the configuration for which you want to view the health-check properties.

--origin-server-pool|-o

Specify the name of the origin-server pool for which you want to view the health-check properties.

Operand

property-name

Specify the name of the property that you want to view (Optional).

You can view the following health check properties:

```
protocol
interval
timeout
failover-threshold
request-method
request-uri
response-code-match
response-body-match
response-body-match-size
dynamic-server-discovery
```

Example

```
tadm get-health-check-prop --user=admin --host=admin.example.com
--password-file=./admin.passwd --port=8989
--no-prompt --config=www.example.org --origin-server-pool=test-pool
interval
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [set-health-check-prop](#)

get-http-listener-prop

Syntax

```
tadm get-http-listener-prop common_options --config=config_name  
--http-listener=name (property_name)*
```

Description

Use this command to view the HTTP listener socket properties.

Options

For information about `common_options`, run the [help](#) command.

`--config|-c`

Specify the configuration for viewing the HTTP listener properties.

`--http-listener|-r`

Specify the name of the HTTP listener.

Operands

`property-name`

Specify the name of the property that you want to view (Optional).

You can view the following HTTP listener properties:

```
enabled  
ip  
port  
acceptor-threads  
server-name  
blocking-io  
handle-protocol-mismatch  
family  
listen-queue-size  
receive-buffer-size  
send-buffer-size  
default-virtual-server-name  
description
```

Note: The properties `family` and `acceptor-threads` can return `default` as a value. Default implies that the server will compute the value of these properties at runtime.

Example

```
tadm get-http-listener-prop --user=admin --host=admin.example.com  
--password-file=./admin.passwd --port=8989  
--no-prompt --config=www.example.org --http-listener=listener1  
blocking-io
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-http-listener](#), [set-http-listener-prop](#), [list-http-listeners](#), [delete-http-listener](#)

get-http-prop

Syntax

```
tadm get-http-prop common_options --config=config_name (property_name)*
```

Description

Use this command to view the HTTP properties.

Options

For information about `common_options`, run the [help](#) command.

`--config|-c`

Specify the name of the configuration for viewing the HTTP properties.

Operands

`property-name`

Specify the name of the property that you want to view (Optional).

You can view the following HTTP properties:

```
version
server-header
etag
request-header-buffer-size
strict-request-headers
discard-misquoted-cookies
max-request-headers
output-buffer-size
max-unchunk-size
unchunk-timeout
io-timeout
request-body-timeout
request-header-timeout
```

Example

```
tadm get-http-prop --user=admin --host=admin.example.com
--password-file=./admin.passwd --port=8989
--no-prompt --config=www.example.org io-timeout
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [set-http-prop](#)

get-keep-alive-prop

Syntax

```
tadm get-keep-alive-prop common_options --config=config_name
(property_name)*
```

Description

Use this command to view the keep-alive properties. The keep-alive or HTTP/1.1 persistent connection handling subsystem in Oracle Traffic Director is designed to be scalable. If the configuration does not conform as required, the performance can be less than optimal if the workload is not persistent (that is, HTTP/1.0 without the KeepAlive header), or for a lightly loaded system that is primarily servicing keep-alive connections.

Options

For information about *common_options*, run the [help](#) command.

```
--config|-c
```

Specify the name of the configuration for viewing the keep-alive properties.

Operands

```
property-name
```

Specify the name of the property that you want to view (Optional).

You can view the following keep-alive properties:

```
enabled
threads
max-connections
timeout
poll-interval
```

Note: The properties *threads* and *max-connections* can return *default* as a value. *Default* implies that the server will compute the value of these properties at runtime.

Example

```
tadm get-keep-alive-prop --user=admin --host=admin.example.com
--password-file=./admin.passwd --port=8989
--no-prompt --config=www.example.org
poll-interval
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [set-keep-alive-prop](#)

get-localization-prop

Syntax

```
tadm get-localization-prop common_options [--vs=vs_name]  
--config=config_name (property_name)*
```

Description

Use this command to view the localization properties. You can configure your browsers to send an `Accept-language` header that describes the language preference for the content that you are accessing. All end-user error messages are also based on the `Accept-language` header.

Options

For information about `common_options`, run the [help](#) command.

--vs|-s

Specify the name of the virtual server.

--config|-c

Specify the configuration for which you want to view the localization properties.

Operands

property-name

Specify the name of the property that you want to view (Optional).

You can view the following localization properties:

default-language

negotiate-client-language

Example

```
tadm get-localization-prop --user=admin --host=admin.example.com  
--password-file=./admin.passwd --port=8989  
--no-prompt --config=www.example.org  
default-language
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [set-localization-prop](#)

get-log

Syntax

```
tadm get-log common_options [--start-date=MM/dd/yyyy:HH:mm:ss]
[--end-date=MM/dd/yyyy:HH:mm:ss]
[--log-level=all|incident_
error:1|error:16|error:32|warning:1|notification:1|trace:1|trace:16|trace:
32] [--num-records=number_of_records]
--vs=vs_name --config=config_name node_host
```

Description

Use this command to get the information about error logs. The error log lists all the errors that the server has encountered since the log file was created. It also contains other server information, such as when the server was started, and a list of unsuccessful login attempts made to the server.

Options

For information about *common_options*, run the [help](#) command.

`--start-date|-S`

Specify the starting date and time from which the log messages must be shown. The format of the date must be `dd/MM/yyyy:HH:mm:ss`.

`--end-date|-E`

Specify the ending date and time until which the log messages must be shown. The format of the date must be `dd/MM/yyyy:HH:mm:ss`.

`--log-level|-l`

Specify the severity of the log messages that must be shown. The value can be `all`, `INCIDENT_ERROR:1`, `ERROR:1`, `ERROR:16`, `ERROR:32`, `WARNING:1`, `TRACE:1`, `TRACE:16`, `TRACE:32`. Default: `NOTIFICATION:1`.

`--num-records|-n`

Specify the number of log messages to be shown from the end of the error log file.

`--vs|-s`

Specify the name of the virtual server.

`--config|-c`

Specify the configuration for which you want to view error log information.

Operands

node-host

Specify the name of the node

Example

```
tadm get-log --user=admin --password-file=./admin.passwd --host=admin.example.com
--port=8989 --no-prompt --vs=soa.example.org --config=www.example.org serverhost
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [get-access-log-prop](#), [rotate-log](#), [get-access-log](#), [enable-access-log](#),
[disable-access-log](#)

get-log-prop

Syntax

```
tadm get-log-prop common_options --config=config_name (property_name)*
```

Description

Use this command to view the log properties.

Options

For information about `common_options`, run the [help](#) command.

`--config|-c`

Specify the name of the configuration for viewing the log properties.

Operands

`property-name`

Specify the name of the property that you want to view (Optional).

You can view the following log properties:

```
log-stdout  
log-stderr  
log-virtual-server-name  
create-console  
log-to-console  
log-to-syslog  
archive-command  
log-level  
log-file
```

Example

```
tadm get-log-prop --user=admin --host=admin.example.com  
--password-file=./admin.passwd --port=8989  
--no-prompt --config=www.example.org log-file
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [set-log-prop](#)

get-origin-server-pool-prop

Syntax

```
tadm get-origin-server-pool-prop common_options --config=config_name
--origin-server-pool=origin_server_pool_name (property_name)*
```

Description

Use this command to view origin-server pool properties.

Options

For information about *common_options*, run the [help](#) command.

--config|-c

Specify the configuration to view the origin-server pool properties.

--origin-serve-pool|-o

Specify the name of the origin-server pool.

Operands

property-name

Specify the name of the property that you want to view (Optional).

You can view the following origin-server pool properties:

```
name
type
family
load-distribution
```

Example

```
tadm get-origin-server-pool-prop --user=admin --host=admin.example.com
--password-file=./admin.passwd --port=8989
--no-prompt --config=www.example.org --origin-server-pool=test-pool
family
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-origin-server-pool](#), [delete-origin-server-pool](#), [list-origin-server-pools](#), [set-origin-server-pool-prop](#)

get-origin-server-prop

Syntax

```
tadm get-origin-server-prop common_options --config=config_name  
--origin-server-pool=origin_server_pool_name  
--origin-server=host:port (property_name)*
```

Description

Use this command to view origin server properties.

Options

For information about `common_options`, run the [help](#) command.

`--config|-c`

Specify the configuration for which you want to view the origin server properties.

`--origin-server-pool|-o`

Specify the name of the origin-server pool for which you want to view the origin server properties.

`--origin-server|-O`

Specify the origin server of the format `host:port`

Operands

`property-name`

Specify the name of the property that you want to view (Optional).

You can view the following origin server properties:

```
enabled  
host  
port  
weight  
backup  
max-connections  
ramp-up-time
```

Example

```
tadm get-origin-server-prop --user=admin --host=admin.example.com  
--password-file=./admin.passwd --port=8989  
--no-prompt --config=www.example.org  
--origin-server-pool=test-pool --origin-server=www.mail2.com:8080  
weight
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-origin-server](#), [delete-origin-server](#), [list-origin-servers](#),
[set-origin-server-prop](#)

get-origin-server-stats

Syntax

```
tadm get-origin-server-stats common_options --config=config_name --node=node_name  
--origin-server-pool=origin_server_pool_name
```

Description

Use this command to view the origin-server statistics for a given configuration.

Options

For information about `common_options`, run the [help](#) command.

`--config|-c`

Specify the configuration for which you want to view the origin server properties.

`--origin-server-pool|-o`

Specify the name of the origin-server pool for which you want to view the origin server properties.

`--node|-n`

Specify the name of the node.

Example

```
tadm get-origin-server-prop --user=admin --host=admin.example.com  
--password-file=./admin.passwd --port=8989  
--no-prompt --config=www.example.org  
--origin-server-pool=test-pool --node=www.mail2.com:8080
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-origin-server](#), [delete-origin-server](#), [list-origin-servers](#),
[set-origin-server-prop](#)

get-perfdump

Syntax

```
tadm get-perfdump common_options --config=config_name --node=node_name
```

Description

Use this command to view the perfdump statistics. The perfdump utility is a Server Application Function (SAF) built into Oracle Traffic Director. The utility collects the Oracle Traffic Director performance data and displays it in ASCII format.

This utility allows you to monitor a greater variety of statistics. With perfdump, the statistics are unified. Rather than monitoring a single process, statistics are multiplied by the number of processes. This gives you a more accurate view of the server performance.

Options

For information about *common_options*, run the [help](#) command.

--node|-n

Specify the name of the node.

--config|-c

Specify the name of the configuration to view the perfdump statistics.

Example

```
tadm get-perfdump --user=admin --password-file=./admin.passwd  
--host=admin.example.com --port=8989 --no-prompt --config=www.example.org  
--node=node1.example.org
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [get-perfdump-prop](#), [enable-perfdump](#), [disable-perfdump](#), [list-nodes](#)

get-perfdump-prop

Syntax

```
tadm get-perfdump-prop common_options --config=config_name --vs=vs_name  
(property_name)*
```

Description

Use this command to get the perfdump properties.

Options

For information about `common_options`, run the [help](#) command.

`--config|-c`

Specify the configuration for which you want to view the perfdump properties.

`--vs|-s`

Specify the name of the virtual server

Operands

`property-name`

Specify the name of the property that you want to view (Optional).

You can view the following perfdump properties:

`enabled`

`uri`

Example

```
tadm get-perfdump-prop --user=admin --host=admin.example.com  
--password-file=./admin.passwd --port=8989  
--no-prompt --config=www.example.org --vs=soa.example.org uri
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [get-perfdump](#), [enable-perfdump](#), [disable-perfdump](#)

get-pkcs11-prop

Syntax

```
tadm get-pkcs11-prop common_options --config=config_name  
(property_name)*
```

Description

Use this command to view the Public Key Cryptography Standard (PKCS#11) properties. PKCS#11 defines the interface used for communication between the Secure Sockets Layer (SSL) and PKCS#11 modules. PKCS#11 modules are used for standards-based connectivity to SSL hardware accelerators.

Options

For information about *common_options*, run the [help](#) command.

--config|-c

Specify the configuration for which you want to view the PKCS#11 properties.

Operands

property-name

Specify the name of the property that you want to view (Optional).

You can view the following PKCS#11 properties:

enabled
allow-bypass
crl-path

Example

```
tadm get-pkcs11-prop --user=admin --host=admin.example.com --port=8989  
--password-file=./admin.passwd --no-prompt  
--config=www.example.org allow-bypass
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [set-pkcs11-prop](#), [list-tokens](#), [set-token-prop](#), [set-token-pin](#)

get-qos-limits-prop

Syntax

```
tadm get-qos-limits-prop common_options --config=config_name  
[--vs=vs_name] (property_name)*
```

Description

Use this command to view the Quality of Service (QoS) limit properties. QoS is the performance limits you set for a server instance or virtual server.

Options

For information about `common_options`, run the [help](#) command.

`--config|-c`

Specify the configuration for which you want to view the QoS limits properties.

`--vs|-s`

Specify the name of the virtual server.

Operands

`property-name`

Specify the name of the property that you want to view (Optional).

You can view the following QoS limits properties:

`enabled`

`max-bps`

`max-connections`

Example

```
tadm get-qos-limits-prop --user=admin --host=admin.example.com  
--password-file=./admin.passwd --port=8989  
--no-prompt --config=www.example.org --vs=soa.example.org  
max-bps
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [set-qos-limits-prop](#), [get-qos-prop](#), [set-qos-prop](#)

get-qos-prop

Syntax

```
tadm get-qos-prop common_options --config=config_name (property_name)*
```

Description

Use this command to view the Quality of Service (QoS) properties.

Options

For information about *common_options*, run the [help](#) command.

--config|-c

Specify the name of the configuration to view the QoS properties.

Operands

property-name

Specify the name of the property that you want to view (Optional).

You can view the following QoS properties:

enabled
interval

Example

```
tadm get-qos-prop --user=admin --password-file=./admin.passwd  
--host=admin.example.com --port=8989 --no-prompt  
--config=www.example.org interval
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [set-qos-prop](#), [get-qos-limits-prop](#), [set-qos-limits-prop](#)

get-request-limit-prop

Syntax

```
tadm get-request-limit-prop common_options --config=config_name  
--vs=vs_name --request-limit=request_limit_name (property_name)*
```

Description

Use this command to view request-limit properties.

Options

For information about `common_options`, run the [help](#) command.

`--config|-c`

Specify the name of the configuration to view the request-limit properties.

`--vs|-s`

Specify the name of the virtual server.

`--request-limit|-l`

Specify the request limit name.

Operands

`property-name`

Specify the name of the property that you want to view (Optional).

You can view the following request limit properties:

```
max-rps  
max-connections  
rps-compute-interval  
condition  
continue-condition  
error-code  
monitor-attribute
```

Example

```
tadm get-request-limit-prop --config=www.example.org  
--vs=soa.example.org --request-limit=request234 error-code
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [list-request-limits](#), [delete-request-limit](#), [create-request-limit](#),
[set-request-limit-prop](#)

get-route-auth-prop

Syntax

```
tadm get-route-auth-prop common_options --config=config_name --vs=vs_name  
--route=route_name
```

Description

Use this command to view the route authentication properties.

Options

For information about *common_options*, run the [help](#) command.

--config|-c

Specify the configuration for which you want to view the route authentication properties.

--vs|-s

Specify the virtual server.

--route|-r

Specify the route name.

Example

```
tadm get-route-auth-prop --user=admin --password-file=./admin.passwd  
--host=admin.example.com --port=8989 --no-prompt  
--config=www.example.org --vs=soa.example.org --route=Rule-1-auth
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [disable-route-auth](#), [enable-route-auth](#), [disable-route-auth](#)

get-route-prop

Syntax

```
tadm get-route-prop common_options --config=config_name --vs=vs_name  
--route=route_name (property_name)*
```

Description

Use this command to view route properties.

Options

For information about `common_options`, run the [help](#) command.

`--config|-c`

Specify the name of the configuration to view the route properties.

`--vs|-s`

Specify the name of the virtual server.

`--route|-r`

Specify the route name that you want to view.

Operands

`property-name`

Specify the name of the property name that you want to view (Optional).

You can view the following route properties:

```
server  
sticky-cookie  
sticky-param  
route-header  
route-cookie  
rewrite-headers  
validate-server-cert  
use-keep-alive  
keep-alive-timeout  
timeout  
always-use-keep-alive  
protocol  
proxy-agent  
origin-server-pool  
from  
to  
websocket-upgrade-enabled  
condition  
log-headers  
buffer-size
```

Example

```
tadm get-route-prop --config=www.example.org --vs=soa.example.org --route=Route323  
route-header
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-route](#), [list-routes](#), [set-route-prop](#), [delete-route](#)

get-snmp-prop

Syntax

```
tadm get-snmp-prop common_options --config=config_name (property_name)*
```

Description

Use this command to view the Simple Network Management Protocol (SNMP) properties.

Options

For information about *common_options*, run the [help](#) command.

`--config|-c`

Specify the name of the configuration to view the SNMP properties.

Operands

property-name

Specify the name of the property that you want to view (Optional).

You can view the following SNMP properties:

```
enabled  
description  
organization  
location  
contact
```

Example

```
tadm get-snmp-prop --config=www.example.org description
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [stop-snmp-subagent](#), [start-snmp-subagent](#), [set-snmp-prop](#)

get-ssl-prop

Syntax

```
tadm get-ssl-prop common_options --config=config_name
(--http-listener=name|tcp-listener=name) (property_name)*
```

Description

Use this command to view the Secure Sockets Layer (SSL) properties for an HTTP and TCP listener. SSL is a software library establishing a secure connection between the client and server. SSL is used to implement HTTPS, the secure version of HTTP.

Options

For information about *common_options*, run the [help](#) command.

--config|-c

Specify the name of the configuration to view the SSL properties.

--http-listener|-r

Specify the name of the configuration to view the SSL properties.

--tcp-listener|-t

Specify the name of the TCP listener.

Operands

property-name

Specify the name of the property that you want to view (Optional).

You can view the following SSL properties:

```
enabled
strict-sni-vs-host-match
tls-session-tickets-enabled
server-cert-nickname
ssl3
tls
client-auth
client-auth-timeout
max-client-auth-data
tls-rollback-detection
```

Example

```
tadm get-ssl-prop --user=admin --host=admin.example.com
--password-file=./admin.passwd --port=8989
--no-prompt --config=www.example.org --http-listener=config1_ls
client-auth-timeout
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [set-ssl-prop](#)

get-ssl-session-cache-prop

Syntax

```
tadm get-ssl-session-cache-prop common_options --config=config_name (property_name)*
```

Description

Use this command to view the properties that are currently defined for caching SSL session data.

Options

For information about *common_options*, run the [help](#) command.

--config|-c

Specify the name of the configuration to view the SSL session cache properties.

Operands

property-name

Specify the name of the property that you want to view (Optional).

You can view the following SSL session cache properties:

enabled

max-entries

max-ssl3-tls-session-age

Example

```
tadm get-ssl-session-cache-prop --user=admin --password-file=./admin.passwd  
--host=admin.example.com --port=8989 --no-prompt  
--config=www.example.org max-entries
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [set-ssl-session-cache-prop](#)

get-stats-prop

Syntax

```
tadm get-stats-prop common_options --config=config_name (property_name)*
```

Description

Use this command to view properties of the statistics collection subsystem.

Options

For information about `common_options`, run the [help](#) command.

`--config|-c`

Specify the name of the configuration for which you want to view the statistics collection subsystem properties.

Operands

`property-name`

Specify the name of the property that you want to view (Optional).

You can view the following statistics collection subsystem properties:

enabled
interval
profiling

Example

```
tadm get-stats-prop --user=admin --host=admin.example.com  
--password-file=./admin.passwd --port=8989  
--no-prompt --config=www.example.org interval
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [set-stats-prop](#)

get-stats-xml

Syntax

```
tadm get-stats-xml common_options --config=config_name --node=node_name
```

Description

Use this command to view the statistics pertaining to an instance of a configuration, in XML format.

Options

For information about *common_options*, run the [help](#) command.

`--config|-c`

Specify the name of the configuration to view the XML statistics.

`--node|-n`

Specify the name of the node.

Example

```
tadm get-stats-xml --user=admin --password-file=./admin.passwd  
--host=admin.example.com --port=8989 --no-prompt  
--config=www.example.org --node=node1.example.org
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [get-stats-xml-prop](#), [enable-stats-xml](#), [disable-stats-xml](#), [list-nodes](#)

get-stats-xml-prop

Syntax

```
tadm get-stats-xml-prop common_options --config=config_name --vs=vs_name  
(property_name)*
```

Description

Use this command to view the properties defined for gathering and reporting statistical data in XML format.

Options

For information about `common_options`, run the [help](#) command.

`--config|-c`

Specify the name of the configuration to view the XML statistics properties.

`--vs|-s`

Specify the name of the virtual server.

Operands

`property-name`

Specify the name of the property that you want to view (Optional).

You can view the following statistical data properties:

`enabled`

`uri`

Example

```
tadm get-stats-xml-prop --user=admin --host=admin.example.com  
--password-file=./admin.passwd --port=8989  
--no-prompt --config=www.example.org --vs=soa.example.org enabled
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [enable-stats-xml](#), [disable-stats-xml](#)

get-tcp-access-log

Syntax

```
tadm get-tcp-access-log common_options [--start-date=MM/dd/yyyy:HH:mm:ss]
[--end-date=MM/dd/yyyy:HH:mm:ss] [--num-records=number_of_records]
--config=config_name node_host
```

Description

Use this command to view the TCP access log entries. The access log records information about requests to and responses from the server. If non-mandatory options are chosen, this command shows the last 100 entries of the default TCP access log file for the selected configuration and node.

Options

For information about *common_options*, run the [help](#) command.

--start-date | -S

Specify the starting date and time from which the log messages must be shown. The start date should be in the dd/MM/yyyy:HH:mm:ss format.

--end-date | -E

Specify the ending date and time until which the log messages must be shown. The end date should be in the d/MM/yyyy:HH:mm:ss format.

--num-records | -n

Specify the number of log messages to be shown.

--config | -c

Specify the name of the configuration for which you want to view the access log information.

Operands

node-host

Specify the name of the host.

Example

```
tadm get-tcp-access-log-prop --user=admin --port=8989
--password-file=./admin.passwd --host=admin.example.com
--no-prompt --config=www.example.org node1
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [enable-tcp-access-log](#), [disable-tcp-access-log](#), [get-tcp-access-log-prop](#)

get-tcp-access-log-prop

Syntax

```
tadm get-tcp-access-log-prop common_options --config=config_name (property_name)*
```

Description

Use this command to view the properties of the TCP access log. The `tcp-access` element defines global level access logging settings.

Options

For information about `common_options`, run the [help](#) command.

`--config|-c`

Specify the name of the configuration for which you would like to view the properties of the TCP access log.

Operands

`property-name`

Specify the name of the property that you want to view (optional).

You can view the following access-log buffer properties:

`enabled`
`file`

Example

```
tadm get-tcp-access-log-prop --user=admin --port=8989  
--password-file=./admin.passwd --host=admin.example.com  
--no-prompt --config=www.example.org enabled
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [enable-tcp-access-log](#), [disable-tcp-access-log](#), [get-tcp-access-log-prop](#)

get-tcp-listener-prop

Syntax

```
tadm get-tcp-listener-prop common_options --config=config_name --tcp-listener=name
(property_name)*
```

Description

Use this command to view the properties of the TCP listener.

Options

For information about *common_options*, run the [help](#) command.

--config|-c

Specify the name of the configuration for which you would like to view the properties of the TCP listener.

--tcp-listener|-t

Specify the name of the TCP listener.

Operands

property-name

Specify the name of the property that you want to view (Optional).

You can view the following properties for the TCP listener:

```
enabled
name
ip
port
family
acceptor-threads
tcp-proxy-name
listen-queue-size
receive-buffer-size
send-buffer-size
description
```

Note: The properties *family* and *acceptor-threads* can return *default* as a value. *Default* implies that the server will compute the value of these properties at runtime.

Example

```
tadm get-tcp-listener-prop --user=admin --port=8989
--password-file=./admin.passwd --host=admin.example.com
--no-prompt --config=www.example.org --tcp-listener=TCP_Listener1
listen-queue-size
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-tcp-listener](#), [delete-tcp-listener](#), [list-tcp-listeners](#), [set-tcp-listener-prop](#)

get-tcp-proxy-prop

Syntax

```
tadm get-tcp-proxy-prop common_options --config=config_name
--tcp-proxy=tcp-proxy-name (property_name)*
```

Description

Use this command to view the properties of the TCP proxy.

Options

For information about *common_options*, run the [help](#) command.

--config|-c

Specify the name of the configuration to view the tcp-proxy properties.

--tcp-proxy|-r

Specify the name of the TCP proxy.

Operands

property-name

Specify the name of the property that you want to view (Optional).

You can view the following properties for the TCP proxy:

enabled

name

session-idle-timeout

origin-server-pool-name

Example

```
tadm get-tcp-proxy-prop --user=admin --port=8989
--password-file=./admin.passwd
--no-prompt --config=www.example.org --tcp-proxy=proxy1 enabled
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-tcp-proxy](#), [delete-tcp-proxy](#), [list-tcp-proxies](#), [set-tcp-proxy-prop](#)

get-tcp-proxy-stats

Syntax

```
tadm get-tcp-proxy-stats common_options --config=config_name
--tcp-proxy=tcp-proxy-name (property_name)*
```

Description

Use this command to view the statistics for a given TCP proxy.

Options

For information about `common_options`, run the [help](#) command.

`--config|-c`

Specify the name of the configuration to view the tcp-proxy properties.

`--tcp-proxy|-r`

Specify the name of the TCP proxy.

Operands

`property-name`

Specify the name of the property that you want to view (Optional).

You can view the following properties for the TCP proxy:

```
interfaces
countActiveConnections
countRequests
countRequestsAborted
countRequestsTimeout
countBytesReceived
countBytesTransmitted
millisecondsConnectionActiveAverage
mode
name
```

Example

```
tadm get-tcp-proxy-prop --user=admin --port=8989
--password-file=./admin.passwd
--no-prompt --config=www.example.org --tcp-proxy=proxy1
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-tcp-proxy](#), [delete-tcp-proxy](#), [list-tcp-proxies](#), [set-tcp-proxy-prop](#)

get-tcp-thread-pool-prop

Syntax

```
tadm get-tcp-thread-pool-prop common_options --config=config_name (property_name)*
```

Description

Use this command to view the properties of the TCP thread pool. The `tcp-thread-pool` element configures the threads that are used to proxy data for upgraded websocket connections and generic TCP connections.

Options

For information about `common_options`, run the [help](#) command.

`--config|-c`

Specify the name of the configuration to view the TCP thread pool properties.

Operands

`property-name`

Specify the name of the property that you want to view (Optional).

enabled
threads
max-connections
timeout
stack-size
poll-interval
buffer-size

Note: The properties `max-connections` and `threads` can return `default` as a value. Default implies that the server will compute the value of this property at runtime.

Example

```
tadm get-tcp-proxy-prop --config=www.example.org enabled
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [set-tcp-thread-pool-prop](#)

get-thread-pool-prop

Syntax

```
tadm get-thread-pool-prop common_options --config=config_name (property_name)*
```

Description

Use this command to view the thread-pool properties. The `thread-pool` element configures the threads used to process HTTP requests. You can use thread pools to allocate a certain number of threads to a specific service. By defining a pool with the maximum number of threads as 1, only one request is allowed to the specified service function.

Options

For information about `common_options`, run the [help](#) command.

`--config|-c`

Specify the name of the configuration to view the thread-pool properties.

Operands

`property-name`

Specify the name of the property that you want to view (Optional).

You can view the following thread-pool properties:

`enabled`
`queue-size`
`min-threads`
`max-threads`
`stack-size`

Note: The properties `max-threads`, `queue-size` and `min-threads` can return default as a value. Default implies that the server will compute the value of these properties at runtime.

Example

```
tadm get-thread-pool-prop --user=admin --port=8989  
--password-file=./admin.passwd --host=admin.example.com  
--no-prompt --config=www.example.org queue-size
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [set-thread-pool-prop](#)

get-virtual-server-prop

Syntax

```
tadm get-virtual-server-prop common_options --config=config_name --vs=vs_name
(property_name)*
```

Description

Use this command to view the properties of a virtual-server.

Options

For information about *common_options*, run the [help](#) command.

--config|-c

Specify the name of the configuration for viewing the virtual-server properties.

--vs|-s

Specify the name of the virtual server.

Operands

property-name

Specify the name of the property that you want to view (Optional).

You can view the following virtual-server properties:

```
enabled
host
default-object-name
http-listener-name
object-file
canonical-server-name
log-file
server-cert-nickname
```

Note: The property *default-object-name* can return *default* as a value. *Default* implies that the server will compute the value of this property at runtime.

Example

```
tadm get-virtual-server-prop --user=admin --port=8989
--password-file=./admin.passwd --host=admin.example.com
--no-prompt --config=www.example.org --vs=soa.example.org
object-file
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-virtual-server](#), [set-virtual-server-prop](#), [list-virtual-servers](#),
[copy-virtual-server](#), [delete-virtual-server](#)

get-virtual-server-stats

Syntax

```
tadm get-virtual-server-stats common_options [--node=node_name] --config=config_name --vs=vs_name
```

Description

Use this command to view the virtual-server statistics for a given configuration.

Options

For information about *common_options*, run the [help](#) command.

--node|-n

Specify the name of the node. If this option is not specified, a collated statistics of the virtual server across all the instances of the configuration is displayed.

--config|-c

Specify the configuration to view the virtual-server statistics.

--vs|-s

Specify the name of virtual server.

Example

```
tadm get-virtual-server-stats --user=admin --host=admin.example.com
--password-file=./admin.passwd --port=8989
--no-prompt --config=www.example.org --vs=soa.example.org
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-virtual-server](#), [set-virtual-server-prop](#), [list-virtual-servers](#), [copy-virtual-server](#), [delete-virtual-server](#), [get-virtual-server-prop](#)

get-webapp-firewall-prop

Syntax

```
tadm get-webapp-firewall-prop common_options --config=config_name --vs=vs_name  
(property_name)*
```

Description

Use this command to view the properties of a web application firewall.

Options

For information about *common_options*, run the [help](#) command.

--config|-c

Specify the configuration to view the virtual-server statistics.

--vs|-s

Specify the name of virtual server.

Operands

property-name

Specify the name of the property that you want to view (Optional).

Example

```
tadm get-webapp-firewall-prop --user=admin  
--host=admin.example.comhost=admin.example.com --password-file=./admin.passwd  
--port=8989  
--no-prompt --config=www.example.org --vs=soa.example.org
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-virtual-server](#), [set-virtual-server-prop](#), [list-virtual-servers](#),
[copy-virtual-server](#), [delete-virtual-server](#), [get-virtual-server-prop](#)

help

Describes the command-line interface.

Syntax

The usage of the `tadm` command-line utility is as follows:

- `tadm --version|-V`
Displays the version of the CLI.
- `tadm --help|-?`
Displays this page in text format.
- `tadm help|-?`
Displays this page in text format.
- `tadm --user|-u admin-user [--password-file|-w]
[admin-passwd-file] [--host|-h admin-host] [--port|-p
admin-port] [--rcfile|-R rcfile]` launches `tadm` in shell mode.
- `tadm subcommand --help`
Displays help for the specified subcommand.
tadm subcommand options
Displays the usage syntax for the specified subcommand.

Syntax Notations

The following conventions are used in this document to show the syntax for command-line options:

- Plain text: Type the text as is.
Example: `option`
- Italicized text: Placeholder for the value of an option or operand. When running CLI commands, you should substitute such placeholders with appropriate values.
Example: *parameter*
- Text in square brackets: Optional argument.
Example: `[argument]`
- Asterisk (*) after text in square brackets: Optional argument; you can specify multiple instances.
Example: `[argument]*`
- Plus symbol (+) after text: Mandatory argument; you can specify multiple instances.
Example: `[argument] +`
- Vertical bar symbol (|) between text: Optional values: specify one of them.
Example: `opt1|opt2`

Description

The command-line interface (CLI) enables you to configure and administer Oracle Traffic Director. Use the command-line tool `tadm` to execute the administration commands.

You can invoke `tadm` in standalone mode, shell mode, or file mode.

- **Standalone mode** – In standalone mode, you can directly invoke the CLI specifying the desired command, options, and operands. On completion of a command, the CLI returns to the shell.

- **Shell mode** — In the shell mode, you can invoke the CLI from a shell that is embedded within `tadm`. On completion of the command, the CLI returns to the shell. You can exit the shell by typing `exit` or `quit`. To enter the Shell mode, `user`, `password`, and `port` options are mandatory. If the port details are not specified, the default port is used. The default port number is 8989.

Example:

```
-----
$ tadm --user=admin --port=8081
--password-file=./admin.passwd

Oracle Traffic Director 11.1.1.6.0 B07/17/2011 20:35

tadm> list-configs

www.example.org
-----
```

- **File mode** — In the file mode, you can create a plain text containing a list of valid commands. The file mode accepts `user` and `password-file` when you invoke `tadm`.

Example:

```
-----
$ cat sample.tcl

set tadm::command false

set x [list-configs]

puts $x

$ tadm --user=admin --password-file=./admin.passwd
--commands-file=sample.tcl
-----
```

tadm Variables

You can also set the following `tadm` variables to modify the overall behavior of `tadm`:

- `tadm::command`: (Applicable only in file mode.) Enables you to output all commands to `stdout` and `stderr`. If this variable is set to `true`, exceptions do not stop the execution of commands, rather, they are printed in the `stdout` and the next command is executed. You can set this variable in the `commands-file`.

```
$ cat commands.tcl
set tadm::command true
set x [list-configs]
puts $x
```

In this example, `commands.tcl` is the name of the file which contains a list of valid commands.

-
- `tadm::savehist`: (Applicable only in the shell mode.) If set to `true`, all `tadm` commands that you execute are saved in the `tadm::histfile` file. The `tadm::histfile` is saved in your home directory. You can set this variable in the `tadm` environment using the `tadm set tadm::savehist true` command.
 - `tadm::file`: This is set to `true` if you are executing the `tadm` commands in file mode.
 - `tadm::tokenize`: If set to `true`, `tadm` parses the log files in a TCL friendly format.
 - `tadm::log_date_format`: Use this variable to define the date format in the log files. The default format is `MM/dd/yyyy:HH:mm:ss`.
 - `tadm::date_format`: Use this variable to define a date format in which a user can enter a date. The default value is the date format of the current locale.
 - `tadm::property_separator`: Use this variable to define the property separators. The default value is the equal sign (`=`). (for example, `tadm> set tadm::property_separator ;`).
 - `tadm::field_separator`: Use this variable to define the field or column separator. The default value is a blank space (). (for example, `tadm> set tadm::field_separator |`).
 - `tadm::field_format`: Use this variable to define the display format of a field or column. Default value: `%-15s`. (for example, `tadm> set tadm::field_format %-15s|`).

Common Options

The term Common Options is used in this document, and in the CLI man pages, to represent the following options:

- Options such as `--user`, `--port`, and `--host`, which are required to connect to the administration server. These options need not be specified in the shell mode.
- Options such as `--echo` and `--verbose`, which are common across several commands.

The following is the full list of common options.

```
--user|-u
```

Specify the user name of the authorized Oracle Traffic Director administrator.

Note: The `--user` | `-u` option is not mandatory for the following CLI commands:

- `configure-server`
- `unconfigure-server`
- `start-snmp-subagent`
- `stop-snmp-subagent`

The `--user` | `-u` option is not required while executing the `reset-admin-password` command.

- When you use the `configure-server` command to create the administration server, `--user` | `-u` option specifies the log-in name for the administration server. It defaults to `admin` while configuring the administration server.
 - When you use the `configure-server` command to create an administration node, `--user` | `-u` option specifies the log-in name that should be used to connect to the administration server. This is a mandatory option while configuring the administration node.
-

`--password-file` | `-w`

Specify the name and the location of the password file. The password file contains the password to authenticate administrators to the administration server. Apart from the administration password, you can also specify other passwords such as `bind-password`, `user-password`, and `token-pin`. If you do not specify this option, you will be prompted for a password when you execute the command. You will also be prompted for password(s) if the required password(s) are not mentioned in the password file you specified.

A sample password file is as follows:

```
tadm_password=tadm-password
tadm_bind_password=bind-password
tadm_user_password=user-password
tadm_token_pin=token-pin
tadm_new_token_pin=new-token-password
tadm_admin_password=admin-password
tadm_<token_name>=token-pin
```

Note: `tadm_<token_name>` is applicable only for the `start-instance` command. You can use `tadm_<token_name>` to set multiple token pins to start instances on multiple nodes.

For example, a default token named `internal` is configured for any instance. The entry for the default token in the password-file will be `tadm_internal=88888888`.

`--host` | `-h`

Specify the name of the computer on which the administration server is running. The default host is `localhost`.

Note: This option is required only if you are connecting to the administration server remotely. The `--host | -h` option is not required while executing the `reset-admin-password` command.

`--port | -p`

Specify the SSL port number of the administration server. The default port is 8989.

Note: The `--port | -p` option is not required while executing the `reset-admin-password` command.

- If you are creating the administration server using the `configure-server` command, `--port | -p` option specifies the SSL port on which the administration server should listen.
 - If you are creating an administration node using the `configure-server` command, `--port | -p` option specifies the SSL port of the remote administration server with which the administration node should be registered.
-

`--no-ssl | -N`

Specify this option to use a plain text connection to communicate with the administration server. The default connection is SSL.

`--rcfile | -R`

Specify the name of the `rcfile` that must be loaded when you start `tadm`. The default file is `~/.tadmrc`. The `.tadmrc` file is a TCL file that is loaded before any command is executed. You can use the long options as variables by changing the hyphen (-) in the option name to underscore (_) and prefixing it with `tadm`. For example:

- `--config` can be set as `set tadm_config config1`
- `--key-type` can be set as `set tadm_key_type ecc`

A sample `rcfile` is as follows:

```
set tadm_config sampleconfig
set tadm_password mypassword
set tadm_nodehost sample.mail.com
```

`--echo | -e`

Specify this option to print this command on the standard output before executing. This option also prints the default value for all the non-mandatory options that you do not provide in the command.

`--no-prompt | -Q`

If you specify this option, `tadm` will not prompt you for passwords while executing this command. Use this option if you have defined all passwords in a password file and specified the file using the `--password-file` option.

`--verbose | -v`

Specify this option to display a verbose output.

`--command | -C`

Specify the name of the commands file which contains the list of `tadm` commands. For more information about commands file, see the description of the file mode.

Exit Codes

The following exit codes are returned:

- 0 – command executed successfully
- 1 to 4 – connection failure errors
- 10 to 22 – parsing errors
- 33 to 43 – input/output errors
- 44 to 56 – general errors; for example, invalid configuration value
- 76 to 96 – generic back-end errors
- 110 to 123 – errors that are specific to Mbeans
- 125 and above – unknown errors

install-cert

Syntax

```
tadm install-cert common_options [--token=name] [--file-on-server]
--config=config_name --cert-type=server|chain|ca [--nickname=nick_name] cert_file
```

Description

Use this command to install a certificate. You should have the server certificate text (ASCII) in a file issued by the certificate authority (CA).

Options

For information about *common_options*, run the [help](#) command.

--token|-t

Specify the token (cryptographic device) on which the certificate should be installed.

--file-on-server|-f

If you specify this option, the server certificate is available on the administrator server. If you do not specify this option, the file is assumed to be available on the client machine and will be uploaded to the server.

--config|-c

Specify the name of the configuration for which you are installing the certificate.

--cert-type|-y

Specify the type of certificate. The values can be *server*, *chain*, or *ca*.

- *server* — Type of certificate that is installed is a server certificate. This certificate should be requested from the same configuration and token which is being installed.
- *chain* — Type of certificate that is installed is a CA chain certificate. This certificate chain contains one or more intermediate CAs.
- *ca* — Type of certificate that is installed is a CA certificate.

--nickname|-n

Specify the nickname (short name) of the certificate. This option is required only for the *server* type certificate.

Operands

cert-file

Specify the name of the file that stores the certificate on the server.

Example

```
tadm install-cert --user=admin --host=admin.example.com --port=8989
--prompt=false --password-file=./admin.pwd --config=www.example.org
--cert-type=server --nickname=cert1 certbin.req
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-cert-request](#), [list-certs](#), [delete-cert](#), [get-cert-prop](#), [set-cert-trust-prop](#),
[create-selfsigned-cert](#)

install-crl

Syntax

```
tadm install-crl common_options [--file-on-server] --config=config_name crl_file
```

Description

Use this command to install a Certificate Revocation List (CRL). A CRL is a revocation list provided by a certificate authority (CA). A CRL lists all certificates that either client or server users should no longer trust. When the data in a certificate changes, the certificate is revoked.

Options

For information about *common_options*, run the [help](#) command.

`--file-on-server|-f`

If you specify this option, the CRL file is available on the administration server computer. If you do not specify this option, the CRL file is assumed to be available on the client machine and will be uploaded to the server.

`--config|-c`

Specify the name of the configuration where you want to install the CRL.

Operands

crl-file

Specify the full path of the CRL file that you want to install.

Example

```
tadm install-crl --user=admin --host=admin.example.com
--password-file=./admin.passwd --port=8989
--no-prompt --config=www.example.org ServerSign.crl
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [list-crls](#), [get-crl-prop](#), [delete-crl](#)

install-webapp-firewall-ruleset

Syntax

```
tadm install-webapp-firewall-ruleset common_options [--file-on-server]
--config=config_name --vs=vs_name ruleset_file
```

Description

Use this command to install a web application firewall ruleset. The `webapp-firewall-ruleset` element configures the path to a WAF configuration file.

Options

For information about `common_options`, run the [help](#) command.

`--file-on-server|-f`

If you specify this option, the ruleset file is available on the administration server host. If you do not specify this option, the file is assumed to be available on the client machine and will be uploaded to the server.

`--config|-c`

Specify the name of the configuration where you want to install the web application firewall ruleset.

`--vs|-s`

Specify the name of the virtual server.

Operands

`ruleset-file`

Specify the full path of the ruleset file. This file must be placed in a ruleset subdirectory within the config directory of an instance. In addition, the `server.xml` must be updated to include this directory.

Example

```
tadm install-webapp-firewall-ruleset --user=admin --host=admin.example.com
--password-file=./admin.passwd --port=8989
--config=www.example.org /tmp/waf-rule.conf
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [delete-webapp-firewall-ruleset](#), [list-webapp-firewall-rulesets](#)

list-backups

Syntax

```
tadm list-backups common_options [--all] --config=config_name
```

Description

Use this command to list the backups of the specified configuration.

Options

For information about *common_options*, run the [help](#) command.

--all|-l

If you specify this option, the command displays the backup date for each backup configuration.

--config|-c

Specify the configuration for which you want to list backups.

Example

```
tadm list-backups --user=admin --host=admin.example.com  
--password-file=./admin.passwd --port=8989  
--no-prompt --config=www.example.org
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [restore-config](#)

list-cache-rules

Syntax

```
tadm list-cache-rules common_options [--all] --config=config_name --vs=vs_name
```

Description

Use this command to view a list of caching rules defined for the specified virtual server.

Options

For information about *common_options*, run the [help](#) command.

--all|-l

If you specify this option, the command displays the condition for each caching rule defined for the specified virtual server.

--config|-c

Specify the configuration for which you want to list cache rules.

--vs|-s

Specify the name of the virtual server.

Example

```
tadm list-cache-rules --user=admin --host=admin.example.com
--password-file=./admin.passwd --port=8989
--no-prompt --config=www.example.org
--vs=soa.example.org
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-cache-rule](#), [delete-cache-rule](#)

list-certs

Syntax

```
tadm list-certs common_options [--all] [--token=name] [--cert-type=(server|ca;  
default is 'server')] --config=config_name
```

Description

Use this command to list all certificates for a configuration. The `list-certs` command prompts for a token password if the token is password protected.

Options

For information about `common_options`, run the [help](#) command.

`--all|-l`

If you specify this option, the command displays the issue name and expiry date for each certificate in the configuration.

`--token|-t`

Specify the token (cryptographic device), that contains the encrypted public key.

`--cert-type|-y`

Specify the value as `server` to list the server certificates, or `ca` to list the certificate authority (CA) certificates.

`--config|-c`

Specify the name of the configuration for which you want to list the certificates.

Example

```
tadm list-certs --user=admin --host=admin.example.com --port=8989  
--prompt=false --config=www.example.org
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-cert-request](#), [delete-cert](#), [install-cert](#), [get-cert-prop](#), [set-cert-trust-prop](#), [create-selfsigned-cert](#)

list-ciphers

Syntax

```
tadm list-ciphers common_options [--all] --config=config_name  
(--http-listener=name|--tcp-listener=name)
```

Description

Use this command to list the SSL ciphers that Oracle Traffic Director supports.

Options

For information about `common_options`, run the [help](#) command.

--all|-l

If you specify this option, the command displays whether the SSL ciphers are enabled in a configuration.

--config|-c

Specify the name of the configuration for which you want to list the ciphers.

--http-listener|-r

Specify the name of the HTTP listener.

--tcp-listener|-t

Specify the name of the TCP listener.

Example

```
tadm list-ciphers --user=admin --password-file=./admin.passwd  
--host=admin.example.com --port=8989 --no-prompt  
--config=www.example.org --http-listener=http-listener-1
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [enable-ciphers](#), [disable-ciphers](#)

list-compression-rules

Syntax

```
tadm list-compression-rules common_options [--all] --config=config_name  
--vs=vs_name
```

Description

Use this command to list compression rules defined for the specified virtual server.

Options

For information about *common_options*, run the [help](#) command.

--all|-l

If you specify this option, the command displays the condition for each compression rule configuration.

--config|-c

Specify the configuration name for which you want to list compression rules.

--vs|-s

Specify the name of the virtual server.

Example

```
tadm list-compression-rules --user=admin --password-file=./admin.passwd  
--host=admin.example.com --port=8989 --no-prompt  
--config=www.example.org --vs=soa.example.org
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-compression-rule](#), [delete-compression-rule](#), [set-compression-rule-prop](#),
[get-compression-rule-prop](#)

list-configs

Syntax

```
tadm list-configs common_options [--all]
```

Description

Use this command to list all existing configurations.

Options

For information about *common_options*, run the [help](#) command.

`--all|-l`

If you specify this option, the command displays the deployment status for each configuration.

Example

```
tadm list-configs --user=admin --password-file=./admin.passwd  
--host=admin.example.com --port=8989 --no-prompt
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-config](#), [deploy-config](#), [copy-config](#), [pull-config](#), [set-config-file](#),
[delete-config](#), [restore-config](#), [get-config-file](#), [list-config-files](#)

list-config-files

Syntax

```
tadm list-config-files common_options --config=config_name
```

Description

Use this command to list configuration files pertaining to the specified configuration.

Options

For information about *common_options*, run the [help](#) command.

`--config|-c`

Specify the name of the configuration for listing all the configuration files.

Example

```
tadm list-config-files --user=admin --host=admin.example.com  
--password-file=./admin.passwd --port=8989  
--no-prompt --config=www.example.org
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-config](#), [deploy-config](#), [copy-config](#), [pull-config](#), [set-config-file](#),
[delete-config](#), [restore-config](#), [get-config-file](#), [list-configs](#)

list-crls

Syntax

```
tadm list-crls common_options [--all] --config=config_name
```

Description

Use this command to list the CRLs for a specified configuration.

Options

For information about *common_options*, run the [help](#) command.

--all|-l

If you specify this option, the command displays the next update information for each CRL configuration.

--config|-c

Specify the name of the configuration for which you want to view the CRLs.

Example

```
tadm list-crls --user=admin --password-file=./admin.passwd  
--host=admin.example.com --port=8989 --no-prompt  
--config=www.example.org
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [install-crl](#), [delete-crl](#), [get-crl-prop](#)

list-error-pages

Syntax

```
tadm list-error-pages common_options [--all] --config=config_name  
--vs=vs_name
```

Description

Use this command to list the error codes for which error pages are defined.

Options

For information about *common_options*, run the [help](#) command.

--all|-l

If you specify this option, the command displays the error page for each error code configuration.

--config|-c

Specify the name of the configuration for which you want to list the error pages.

--vs|-s

Specify the name of the virtual server.

Example

```
tadm list-error-pages --user=admin --password-file=./admin.passwd  
--host=admin.example.com --port=8989 --no-prompt  
--config=www.example.org --vs=soa.example.org
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-error-page](#), [delete-error-page](#)

list-events

Syntax

```
tadm list-events common_options [--all] --config=config_name
```

Description

Use this command to list all scheduled events for a configuration.

Options

For information about *common_options*, run the [help](#) command.

--all|-l

If you specify this option, the command displays enabled, day of the month, month, day of week, time, and interval for each scheduled event in a configuration.

--config|-c

Specify the name of the configuration for which you want to list the events.

Example

```
tadm list-events --user=admin --password-file=./admin.passwd  
--host=admin.example.com --port=8989 --no-prompt  
--config=www.example.org
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-event](#), [delete-event](#), [disable-event](#), [enable-event](#)

list-failover-groups

Syntax

```
tadm list-failover-groups common_options --config=config_name [--all]
```

Description

Use this command to view a list of the failover groups defined for a configuration.

Options

For information about *common_options*, run the [help](#) command.

`--config|-c`

Specify the name of the configuration for which you want to list the failover groups.

`--all|-l`

If you specify this option, the command displays the primary and the backup nodes of the failover groups.

Example

```
tadm list-failover-groups --config=soa --verbose --all
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-failover-group](#), [delete-failover-group](#), [set-failover-group-primary](#), [get-failover-group-prop](#)

list-http-listeners

Syntax

```
tadm list-http-listeners common_options [--all] --config=config_name
```

Description

Use this command to list the names of the HTTP listeners defined for the configuration, and (optionally) the IP address and port number for each listener.

Options

For information about *common_options*, run the [help](#) command.

--all|-l

If you specify this option, the command displays the IP and port for each HTTP listener configuration.

--config|-c

Specify the name of the configuration for which you want to list the HTTP listeners.

Example

```
tadm list-http-listeners --user=admin --host=admin.example.com  
--password-file=./admin.passwd --port=8989  
--no-prompt --config=www.example.org
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-http-listener](#), [set-http-listener-prop](#), [set-http-listener-prop](#), [delete-http-listener](#)

list-instances

Syntax

```
tadm list-instances common_options [--all] ( --config=name | --node=name )
```

Description

Use this command to list all instances.

- If you specify the configuration name, the command lists all nodes on which the configuration is deployed.
- If you specify the node, the command lists all configurations deployed on that node.

Note: If a node is service-enabled, then `list-instances` will list `service-name` of the service corresponding to the instance of that node. Note that for `service-name` to appear, you must run `list-instances` with the `--all` option.

Options

For information about `common_options`, run the [help](#) command.

`--node|-n`

Specify the host name of the node for which you want to list the configurations.

`--all|-l`

If you specify this option, the command displays instance status and if the instance has service for each instance in the configuration.

`--config|-c`

Specify the name of the configuration for which you want to list the nodes.

Example

```
tadm list-instances --user=admin --password-file=./admin.passwd
--host=admin.example.com --port=8989 --no-prompt
--config=www.example.org
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-instance](#), [delete-instance](#), [start-instance](#), [stop-instance](#), [restart-instance](#), [reconfig-instance](#), [list-nodes](#), [remove-node](#)

list-nodes

Syntax

```
tadm list-nodes common_options [--all]
```

Description

Use this command to list all the nodes that are registered with the administration server. This command also lists the node status.

Options

For information about *common_options*, run the [help](#) command.

--all|-l

If you specify this option, the command displays the node port, node online, and node description for each node that is registered with the administration server.

Example

```
tadm list-nodes --user=admin --password-file=./admin.passwd  
--host=admin.example.com --port=8989 --no-prompt
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [remove-node](#)

list-origin-servers

Syntax

```
tadm list-origin-servers common_options [--all] --config=config_name
--origin-server-pool=origin_server_pool_name
```

Description

Use this command to view a list of origin-servers defined in a pool.

Options

For information about *common_options*, run the [help](#) command.

--all|-l

If you specify this option, the command displays weight, enabled, and backup for each origin server defined in a pool.

--config|-c

Specify the configuration for which you want to list the origin-servers.

--origin-server-pool|-o

Specify the name of the origin-server pool for which you want to view the origin servers.

Example

```
tadm list-origin-servers --user=admin --host=admin.example.com
--password-file=./admin.passwd --port=8989
--no-prompt --config=www.example.org
--origin-server-pool=test-pool
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-origin-server](#), [delete-origin-server](#), [get-origin-server-prop](#), [set-origin-server-prop](#)

list-origin-server-pools

Syntax

```
tadm list-origin-server-pools common_options [--all] [--type=http|https|tcp]
--config=config_name
```

Description

Use this command to list origin-server pools defined for a configuration.

Options

For information about *common_options*, run the [help](#) command.

--all|-l

If you specify this option, the command displays the origin-server pool type and load distribution for each origin-server pool configuration.

--type|-t

Specify the protocol for which requests are handled by the servers in the pool. If you do not specify the type, all the available origin servers are listed.

--config|-c

Specify the configuration for which you want to list origin-server pools.

Example

```
tadm list-origin-server-pools --user=admin --host=admin.example.com
--password-file=./admin.passwd --port=8989
--no-prompt --type=tcp --config=www.example.org
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [get-origin-server-pool-prop](#), [set-origin-server-pool-prop](#),
[delete-origin-server-pool](#), [create-origin-server-pool](#)

list-proxy-info

Syntax

```
tadm list-proxy-info common_options [--all] --config=config_name  
--vs=vs_name --route=route_name
```

Description

Use this command to view information about the proxy parameters configured for a route.

Options

For information about *common_options*, run the [help](#) command.

--all|-l

If you specify this option, the command displays header and status for each proxy configuration.

--config|-c

Specify the name of the configuration for which you want to list the proxy parameters.

--vs|-s

Specify the name of the virtual server.

--route|-r

Specify the route name for listing the proxy parameters.

Example

```
tadm list-proxy-info --config=www.example.org --vs=soa.example.org --route=Route-1
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [block-proxy-info](#), [forward-proxy-info](#)

list-request-limits

Syntax

```
tadm list-request-limits common_options [--all] --config=config_name  
--vs=vs_name
```

Description

Use this command to list the request limit conditions defined for a virtual server.

Options

For information about *common_options*, run the [help](#) command.

--all|-l

If you specify this option, the command displays the condition for each request limits configuration.

--config|-c

Specify the name of the configuration to list request limits.

--vs|-s

Specify the name of the virtual server.

Example

```
tadm list-request-limits --user=admin --host=admin.example.com  
--password-file=./admin.passwd --port=8989 --no-prompt --config=www.example.org  
--vs=soa.example.org
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [get-request-limit-prop](#), [set-request-limit-prop](#), [delete-request-limit](#),
[create-request-limit](#)

list-routes

Syntax

```
tadm list-routes common_options [--all] --config=config_name  
--vs=vs_name
```

Description

Use this command to list the rules defined for a virtual server.

Options

For information about *common_options*, run the [help](#) command.

--all|-l

If you specify this option, the command displays the condition for each route rule configuration.

--config|-c

Specify the name of the configuration for which you want to list routes.

--vs|-s

Specify the name of the virtual server.

Example

```
tadm list-routes --user=admin --host=admin.example.com  
--password-file=./admin.passwd --port=8989 --no-prompt --config=www.example.org  
--vs=soa.example.org
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-route](#), [delete-route](#), [get-route-prop](#), [set-route-prop](#)

list-tcp-listeners

Syntax

```
tadm list-tcp-listeners common_options [--all] --config=config_name
```

Description

Use this command to list all TCP listeners.

Options

For information about *common_options*, run the [help](#) command.

--all|-l

If you specify this option, the command displays the IP and port for each TCP listener configuration.

--config|-c

Specify the name of the configuration to list all the TCP listeners.

Example

```
tadm list-tcp-listeners --user=admin --password-file=./admin.passwd  
--host=admin.example.com --port=8989 --no-prompt  
--config=www.example.org
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-tcp-listener](#), [delete-tcp-listener](#), [get-tcp-listener-prop](#), [set-tcp-listener-prop](#)

list-tcp-proxies

Syntax

```
tadm list-tcp-proxies common_options [--all] --config=config_name
```

Description

Use this command to list all TCP proxies.

Options

For information about *common_options*, run the [help](#) command.

`--all|-l`

If you specify this option, the command displays all the TCP proxies along with information about the respective server pools.

`--config|-c`

Specify the name of the configuration to list all the TCP proxies.

Example

```
tadm list-tcp-proxies --user=admin --password-file=./admin.passwd  
--host=admin.example.com --port=8989 --no-prompt --all  
--config=www.example.org
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-tcp-proxy](#), [delete-tcp-proxy](#), [get-tcp-proxy-prop](#), [set-tcp-proxy-prop](#)

list-tokens

Syntax

```
tadm list-tokens common_options [--all] --config=config_name
```

Description

Use this command to list all PKCS#11 tokens.

Options

For information about *common_options*, run the [help](#) command.

--all|-l

If you specify this option, the command displays information whether the tokens are enabled and if the token PIN is saved in the *server.xml* file for each PKCS#11 token.

--config|-c

Specify the name of the configuration to list all the tokens.

Example

```
tadm list-tokens --user=admin --password-file=./admin.passwd  
--host=admin.example.com --port=8989 --no-prompt  
--config=www.example.org
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [get-pkcs11-prop](#), [set-pkcs11-prop](#), [set-token-prop](#), [set-token-pin](#)

list-variables

Syntax

```
tadm list-variables common_options [-all] [--vs=vs_name]  
--config=config_name
```

Description

Use this command to list the variables defined for the configuration or for a specific virtual server.

Options

For information about *common_options*, run the [help](#) command.

--all|-l

If you specify this option, the command displays the description for each variable defined in the configuration.

--vs|-s

Specify the name of the virtual server.

--config|-c

Specify the name of the configuration for listing variables.

Example

```
tadm list-variables --user=admin --password-file=./admin.passwd  
--host=admin.example.com --port=8989  
--no-prompt --vs=soa.example.org --config=www.example.org
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-variable](#), [delete-variable](#)

list-virtual-servers

Syntax

```
tadm list-virtual-servers common_options [--all] --config=config_name
```

Description

Use this command to list all virtual-servers defined for a configuration.

Options

For information about *common_options*, run the [help](#) command.

--all|-l

If you specify this option, the command displays the HTTP listener name for each virtual server configuration.

--config|-c

Specify the name of the configuration for which you want to view the virtual servers.

Example

```
tadm list-virtual-servers --user=admin --host=admin.example.com  
--password-file=./admin.passwd --port=8989  
--no-prompt --config=www.example.org
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-virtual-server](#), [set-virtual-server-prop](#), [get-virtual-server-prop](#),
[delete-virtual-server](#), [copy-virtual-server](#)

list-webapp-firewall-rulesets

Syntax

```
tadm list-webapp-firewall-rulesets common_options --config=config_name (--vs=vs_name)
```

Description

Use this command to list all web application firewall rulesets defined for a configuration or for a specific virtual server.

Options

For information about *common_options*, run the [help](#) command.

--config|-c

Specify the name of the configuration for which you wish to view the list of web application firewall rulesets.

--vs|-s

Specify the name of the virtual server.

Example

```
tadm list-webapp-firewall-rulesets --user=admin --host=admin.example.com  
--password-file=./admin.passwd --port=8989  
--no-prompt --config=www.example.org
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [install-webapp-firewall-ruleset](#), [delete-webapp-firewall-ruleset](#)

pull-config

Syntax

```
tadm pull-config common_options --config=config_name node_host
```

Description

Use this command to pull a configuration from any instance of the configuration and overwrite all undeployed configuration changes. You can use this command when an instance is modified manually, so that the manual modification can be reflected in the `config-store` directory.

Caution: Do not edit any file under the `config-store` directory. The files under this directory are created by Oracle Traffic Director for internal use.

Options

For information about `common_options`, run the [help](#) command.

`--config|-c`

Specify the name of the server configuration for pulling configurations.

Operands

`node-host`

Specify the name of the node that hosts the manually modified instance.

Example

```
tadm pull-config --user=admin --password-file=./admin.passwd  
--host=admin.example.com --port=8989 --no-prompt  
--config=www.example.org serverhost
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-config](#), [list-configs](#), [delete-config](#), [copy-config](#), [deploy-config](#), [restore-config](#), [list-config-files](#), [get-config-file](#), [set-config-file](#)

reconfig-instance

Syntax

```
tadm reconfig-instance common_options --config=config_name (node_host)*
```

Description

Use this command to reconfigure server instances. Configuration changes are reflected on instances without a server restart. Only dynamically reconfigurable changes in the configuration take effect.

Changes in the `user`, `temp-path`, `log`, `thread-pool`, `pkcs11`, `stats`, `dns`, `dns-cache`, `ssl-session-cache`, and `access-log-buffer` settings remain the same after a reconfiguration procedure is completed. Any such changes that require restart will be logged when a reconfiguration is done.

Options

For information about `common_options`, run the [help](#) command.

```
--config|-c
```

Specify the name of the configuration to reconfigure server instances.

Operands

```
node-host
```

Specify the name of the node.

Example

```
tadm reconfig-instance --user=admin --password-file=./admin.passwd
--host=admin.example.com --port=8989
--no-prompt --config=www.example.org serverhost
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [delete-instance](#), [list-instances](#), [start-instance](#), [stop-instance](#), [restart-instance](#), [create-instance](#), [list-nodes](#)

remove-node

Syntax

```
tadm remove-node common_options [--force] --node=node_name
```

Description

Use this command to remove a registered node from the administration server. This node does not show up in the list of nodes, as it is no longer managed by the administration server.

Options

For information about *common_options*, run the [help](#) command.

`--force|-f`

Specify this option to remove a node. It will try to delete instances that are deployed on the node. Also, if the node is down, the force option would remove the node.

`--node|-n`

Specify the name of the node that you want to remove.

Example

```
tadm remove-node --user=admin --password-file=./admin.passwd  
--host=admin.example.com --port=8989 --no-prompt  
--node=node1.example.org
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [list-nodes](#)

renew-admin-certs

Syntax

```
tadm renew-admin-certs common_options [--validity=num_of_months]
```

Description

Use this command to renew the administration certificates with the nicknames Admin-CA-Cert, Admin-Server-Cert, and Admin-Client-Cert. This command also updates the nodes that are currently running and are accessible with the renewed certificates.

Oracle recommends that after you run this command, you stop and restart the administration servers and nodes so that the new certificates take effect.

Options

For information about *common_options*, run the [help](#) command.

--validity|-d

Specify the validity period (in months) for the administration certificates. The default validity period is 120 months.

Example

```
tadm renew-admin-certs --user=admin --host=admin.example.com
--password-file=./admin.passwd --port=8989
--no-prompt --validity=120
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [reset-admin-password](#), [renew-node-certs](#)

renew-node-certs

Syntax

```
tadm renew-node-certs common_options --instance-home=instance_home
```

Description

This command must be invoked on an administration node. Use this command to renew the authentication certificates from the administration server and install them on the administration node. This is required for securely communicating with the administration server. You must use this command when the node was not running at the time of renewing the authentication certificates for the administration server. You must restart the administration node for the changes to take effect.

Options

For information about `common_options`, run the [help](#) command.

`--instance-home|-i`

Indicates the location where the server instances can be found.

Example

```
tadm renew-node-certs --instance-home=/documents/nodes
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [renew-admin-certs](#), [reset-admin-password](#), [restart-admin](#)

reset-admin-password

Syntax

```
tadm reset-admin-password common_options --instance-home=instance_home
```

Description

Use this command to reset the administrator server password. This command should be used locally where the administrator server is installed. This command does not prompt for the old password.

Note: This command can be executed only when the authentication database is a keyfile, which is the default setting.

Options

For information about *common_options*, run the [help](#) command.

--instance-home | -i

Indicates the location where the server instances can be found.

Example

```
tadm reset-admin-password --instance-home=/home/otd
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [renew-admin-certs](#)

restart-admin

Syntax

```
tadm restart-admin common_options node_host
```

Description

Use this command to restart the administration server or node.

Note: To restart an instance, use the [restart-instance](#) command.

Options

For information about *common_options*, run the [help](#) command.

Operands

node-host

Specify the host name of the administration server or node.

Example

```
tadm restart-admin --user=admin --host=admin.example.com
--password-file=./admin.passwd --port=8989
--no-prompt serverhost
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [list-nodes](#)

restart-instance

Syntax

```
tadm restart-instance common_options --config=config_name (node_host)*
```

Description

Use this command to restart one or more instances of a configuration.

Options

For information about *common_options*, run the [help](#) command.

--config|-c

Specify the configuration for which you want to restart instances.

Operands

node-host

Specify the host name of the node (or nodes) on which the instance that you want to restart is running. When specifying multiple nodes, separate the host names by spaces. If no nodes are specified, all instances running on the specified configuration are restarted. If the instance on any node is not running, this command will display an error.

Example

```
tadm restart-instance --user=admin  
--password-file=./admin.passwd --host=admin.example.com  
--port=8989 --no-prompt --config=www.example.org serverhost
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-instance](#), [delete-instance](#), [list-instances](#), [start-instance](#), [stop-instance](#),
[list-nodes](#)

restore-config

Syntax

```
tadm restore-config common_options --from-backup=backup_id config_name
```

Description

Use this command to restore a configuration to a specific earlier state by using a backup.

Options

For information about *common_options*, run the [help](#) command.

`--from-backup|-b`

Specify the ID of the backup configuration. You can view a list of the available backups by running the `list-configs` command.

Operand

config-name

Specify the configuration that you want to restore to an earlier state.

Example

```
tadm restore-config --user=admin --host=admin.example.com  
--password-file=./admin.passwd --port=8989  
--no-prompt --from-backup=20110813_084722 www.example.org
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-config](#), [deploy-config](#), [copy-config](#), [pull-config](#), [set-config-file](#), [delete-config](#), [list-configs](#), [get-config-file](#), [list-config-files](#)

rotate-log

Syntax

```
tadm rotate-log common_options --config=config_name (node_host)*
```

Description

Use this command to rotate the log files. The server saves the old log files and marks the saved files with a name that includes the date and time when they were saved.

Note: You can set up the log files to be automatically archived. At a certain time, or after a specified interval, the server rotates the logs. Use [create-event](#) command to generate new log files for the events that are created.

Options

For information about *common_options*, run the [help](#) command.

--config|-c

Specify the configuration for which you want to rotate logs.

Operands

node-host

Specify the host names of one or more nodes for which you want to rotate the log files.

Example

```
tadm rotate-log --user=admin --password-file=./admin.passwd  
--host=admin.example.com --port=8989 --no-prompt --config=www.example.org  
serverhost
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [list-nodes](#)

set-access-log-buffer-prop

Syntax

```
tadm set-access-log-buffer-prop common_options --config=config_name (property_name=property_value)+
```

Description

Use this command to set the properties of the access-log buffer.

Options

For information about `common_options`, run the [help](#) command.

`--config|-c`

Specify the configuration for which you want to set the properties of the access-log buffer.

Operands

`property-name=property-value`

Specify `name=value` pairs for one or more properties that you want to define. The `name=value` pairs should be separated by spaces.

You can set the following set-access-log buffer properties:

`enabled`: Specifies whether the server should buffer the access log entries.

Values: `true`, `false`. Default: `true`

`buffer-size`: The size (in bytes) of individual access log buffers.

Values: 4096 to 1048576.

`direct-io`: Indicates whether the file system should cache access-log writes. The default value, `false`, indicates that the file system should cache access log writes. Setting the value to `true` indicates that the file system should not cache access log writes. The setting is purely advisory; either the server or the operating system may choose to ignore it.

Values: `true`, `false`. Default: `false`

`max-buffers`: Specifies the maximum number of access log buffers per server.

Values: 1 to 65536.

`max-buffers-per-file`: Specifies the maximum number of access log buffers per access-log file.

Values: 1 to 128.

Note: The property `max-buffers-per-file` can accept default as a value. Default implies that the server will compute the value of this property at runtime.

`max-age`: The maximum time (in seconds) to buffer a given access-log entry.

Values: 0.001 to 3600.

To reset a property to its default value, do not provide a property value.

For example, `property-name=<empty_string>`

Example

```
tadm set-access-log-buffer-prop --user=admin --password-file=./admin.passwd  
--host=admin.example.com --port=8989 --no-prompt  
--config=www.example.org max-age=1000
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [get-access-log-buffer-prop](#), [enable-access-log](#), [disable-access-log](#), [get-access-log](#), [get-log](#), [get-log-prop](#), [set-log-prop](#), [rotate-log](#)

set-admin-prop

Syntax

```
tadm set-admin-prop common_options [--set-password] [--node=node_name] (property_name=property_value)+
```

Description

Use this command to set the properties of the administration server or a node.

Options

For information about `common_options`, run the [help](#) command.

`--set-password|-r`

Specify this option to change the administration server password.

`--node|-n`

Specify the name of the node. To change properties of an administration node, specify the node. To change properties of the administration server, it not mandatory to specify the node.

Operands

`property-name=property-value`

Specify `name=value` pairs for one or more properties that you want to define. The `name=value` pairs should be separated by spaces.

You can set the following administration properties:

`java-home`: Specifies the home directory where the Oracle Traffic Director application is installed.

Values: Must be a text string. Default: `ORACLE_HOME/jdk` directory.

`admin-user`: Specifies the administration server user which will be used to log into the administration server

Values: Must be a text string.

`server-user`: Specifies the Unix user ID with which administration server/node is running.

Values: Must be a text string.

Note: If a node is service-enabled, the `server-user` property of the node cannot be changed to a non-root user.

`ssl-port`: Specifies the SSL port for the administration server/node.

Values: 1 to 65535. Default: 8989.

`log-file`: Specifies the name and location of the log file.

Values: User defined name and location. Default: `../log/errors`.

`log-level`: Specifies the log verbosity for the server as a whole.

Values: `INCIDENT_ERROR:1, ERROR:1, ERROR:16, ERROR:32, WARNING:1, TRACE:1, TRACE:16, TRACE:32`. Default: `NOTIFICATION:1`.

`server-log-file`: Specifies the name and location of the server log file.
 Values: User defined name and location. Default: `../logs/server.log`

`access-log-file`: Specifies the name and location of the access log file.
 Values: User defined name and location. Default: `../logs/access.log`

`description`: Specifies the description of the administration server.
 Values: Must be a text string.

`bind-ip`: Specifies the IP address of the administration server's default listener.
 Values: Must be a text string.

To reset a property to its default value, do not provide a property value.
 For example, `property-name=<empty_string>`

Example

```
tadm set-admin-prop --user=admin --host=admin.example.com
--password-file=./admin.passwd --port=8989
--no-prompt "--node=node1.example.com
access-log-file=../logs/www_example_com_access.log
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [get-admin-prop](#), [restart-admin](#), [stop-admin](#), [list-nodes](#)

set-cache-prop

Syntax

```
tadm set-cache-prop common_options --config=config_name (property_name=property_value)+
```

Description

Use this command to define or change caching properties for a configuration.

Options

For information about `common_options`, run the [help](#) command.

`--config|-c`

Specify the name of the configuration to set the cache properties.

Operands

`property-name=property-value`

Specify `name=value` pairs for one or more properties that you want to define. The `name=value` pairs should be separated by spaces.

You can set the following cache properties:

`enabled`: Specifies whether the server should change caching properties.

Values: `true`, `false`. Default: `true`.

`max-entries`: Specifies the maximum number of objects for which the content should be cached.

Values: 1 to 1073741824. Default: 1024.

`replacement`: Specifies the algorithm for cache replacement.

Values: `lru`, `lfu`, and `false`. Default: `lru`.

`max-heap-object-size`: Specifies the maximum size of objects that should be cached. Objects larger than the specified size are not cached.

Values: 0 to 214783647. Default: 512 KB.

`max-heap-space`: Specifies the maximum number (in bytes) of heap that is used for caching response objects. Values: 0 to 1099511627776. Default: 10 MB.

To reset a property to its default value, do not provide a property value.

For example, `property-name=<empty_string>`

Example

```
tadm set-cache-prop --user=admin --host=admin.example.com
--password-file=./admin.pwd --port=8989
--prompt=false --config=www.example.org max-heap-object-size=1237
max-entries=1293
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [get-cache-prop](#)

set-cache-rule-prop

Syntax

```
tadm set-cache-rule-prop common_options --config=config_name --vs=vs_name  
--cache-rule=cache_rule_name (property_name=property_value)+
```

Description

Use this command to set up the cache rule properties.

Options

For information about `common_options`, run the [help](#) command.

`--config|-c`

Specify the name of the configuration for which you want to set cache rule properties.

`--vs|-s`

Specify the virtual server.

`--cache-rule|-r`

Specify the cache rule name.

Operands

`property-name=property-value`

Specify `name=value` pairs for one or more properties that you want to define. The `name=value` pairs should be separated by spaces.

You can set the following cache rule properties:

`enabled`: Specifies whether the caching rule is enabled.

Values: `true`, `false`. Default: `false`.

`max-reload-interval`: Specifies the maximum time (in seconds) allowed between consecutive up-to-date checks.

Values: Positive integer. Default: 3600.

`min-reload-interval`: Specifies the minimum time (in seconds) allowed between consecutive up-to-date checks of a cached document.

Values: Positive integer. Default: 0.

`last-modified-factor`: Represents the factor used in estimating the expiry time, which defines how long a document will be up-to-date based on time it was last modified. This property is used only when the explicit age of the document is not available

Values: Floating. Positive floating value from 0 to any large value.

`min-object-size`: Specifies the minimum size (in bytes) of any document to be cached.

Values: Positive integer. Must be less than `max-object-size`.

`max-object-size`: The maximum size, in bytes, of any document to be cached. This setting enables users to limit the maximum size of cached documents, so that no single document can take too much space. This value cannot exceed the value of `max-heap-object-size`.

Values: Positive integer.

`query-maxlen`: Specifies the number of characters in the query string. If this property is set to 0, URIs with query strings are not cached.

Values: Positive integer. Default: 0

`compression`: If this property value is set to `true`, the document is compressed before storing in the cache.

Values: `true`, `false`. Default: `false`.

`cache-https-response`: If this property value is set to `true`, responses from the HTTPS servers are also cached.

Values: `true`, `false`. Default: `false`.

To reset a property to its default value, do not provide a property value.

For example, `property-name=<empty_string>`

Example

```
tadm set-cache-rule-prop --config=www.example.org
--vs=soa.example.org --cache-rule=cache-rule-1 max-reload-interval=2
min-object-size=150
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [set-cache-prop](#), [get-cache-rule-prop](#)

set-cert-trust-prop

Syntax

```
tadm set-cert-trust-prop common_options [--token=name]  
--config=config_name --nickname=nick_name (property_name=property_value) +
```

Description

Use this command to set the certificate trust properties. A certificate is issued and digitally signed by a certificate authority (CA). You decide which CAs you trust enough to serve as verifiers of other users' identity. The `set-cert-trust-prop` command prompts for a token password if the token is password protected.

Options

For information about `common_options`, run the [help](#) command.

`--token|-t`

Specify the token (cryptographic device), which contains the encrypted public key.

`--config|-c`

Specify the name of the configuration to set certificate trust properties.

`--nickname|-n`

Specify the short name (nickname) of the certificate for which you want to set trust properties.

Operands

`property-name=property-value`

Specify `name=value` pairs for one or more properties that you want to define. The `name=value` pairs should be separated by spaces.

You can set the following certificate trust properties:

Nickname: Specify the nickname for the certificate trust.

Value: Must be a text string.

Subject: Specify the subject for the certificate trust.

Value: Must be a text string.

Issuer: Specify the issuer information for the certificate trust.

Value: Must be a text string.

Valid From: Specify the certificate validity start date.

Value: Must be a text string.

Valid Till: Specify the certificate validity end date.

Value: Must be a text string.

Fingerprint: Specify the fingerprint information for the certificate trust.

Value: Must be a text string.

Serial Number: Specify the serial number information for the certificate trust.

Value: Must be a text string.

Trusted to sign Client Certificates: Specify whether the CA is trusted to sign client certificates.

Values: `true`, `false`. Default: `true`

Trusted to sign Server Certificates: Specify whether the CA is trusted to sign server certificates.

Values: true, false. Default: true

To reset a property to its default value, do not provide a property value.

For example, `property-name=<empty_string>`

Example

```
tadm set-cert-trust-prop --user=admin --host=admin.example.com
--password-file=./admin.passwd --port=8989
--prompt=false --config=www.example.org Trusted to sign client certificates=true
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [get-cert-prop](#), [create-cert-request](#), [list-certs](#), [install-cert](#), [delete-cert](#), [create-selfsigned-cert](#)

set-compression-rule-prop

Syntax

```
set-compression-rule-prop common_options --config=config_name --vs=vs_name  
--rule=compression_rule_name (property_name=property_value)+
```

Description

Use this command to set or change properties of a compression rule for a virtual server.

Options

For information about `common_options`, run the [help](#) command.

--config|-c

Specify the configuration name for which you want to set compression rule properties.

--vs|-s

Specify the name of the virtual server.

--rule|-r

Specify the compression rule name.

Operand

`property-name=property-value`

Specify name=value pairs for one or more properties that you want to define. The name=value pairs should be separated by spaces.

You can set the following compression rule properties:

`insert-vary-header`: Select to insert a vary:Accept-encoding header.
Values: true, false. Default: true.

`compression-level`: Specifies the compression level for the virtual server.
Values: 1 to 9. Specifying 1 yields better speed and specifying 9 yields best compression.

Note: The property `compression-level` can accept default as a value. Default implies that the server will compute the value of this property at runtime.

`fragment-size`: Specifies the memory fragment size (in bytes) that is used by the compression library to control the compression rate.
Values: Any integer.

To reset a property to its default value, do not provide a property value.
For example, `property-name=<empty_string>`

Example

```
tadm set-compression-rule-prop --config=www.example.org  
--vs=soa.example.org --rule=Compression34 compression-level=9
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-compression-rule](#), [delete-compression-rule](#), [list-compression-rules](#),
[get-compression-rule-prop](#)

set-config-file

Syntax

```
tadm set-config-file common_options --config=config_name --upload-file=local_file_to_upload file_name
```

Description

Use this command to change one of the files of a configuration or to add a file to the configuration.

Options

For information about `common_options`, run the [help](#) command.

`--config|-c`

Specify the name of the configuration for which you want to add or replace a configuration file.

`--upload-file|-o`

Specify the name of the local file to be uploaded to the configuration directory.

Operands

`file-name`

Specify the name of the configuration file.

Example

```
tadm set-config-file --user=admin --host=admin.example.com  
--password-file=./admin.passwd --port=8989 --no-prompt --config=www.example.org  
--upload-file=obj.conf obj.conf
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-config](#), [list-configs](#), [delete-config](#), [copy-config](#), [pull-config](#), [restore-config](#), [list-config-files](#), [get-config-file](#), [deploy-config](#)

set-config-prop

Syntax

```
set-config-prop common_options --config=config_name (property_name=property_value)+
```

Description

Use this command to set the configuration file properties.

Options

For information about *common_options*, run the [help](#) command.

```
--config|-c
```

Specify the name of the configuration for which you want to change properties.

Operands

```
property-name=property-value
```

Specify name=value pairs for one or more properties that you want to define. The name=value pairs should be separated by spaces.

You can set the following configuration file properties:

user: Specifies the user ID with which the server runs.

Values: User ID

temp-path: Specifies the location where the server stores its temporary files.

Values: Any valid directory.

webapp-firewall-ruleset: Specifies the location where the Web Application Firewall (WAF) ruleset files are stored.

Values: Any valid directory where the WAF ruleset files are stored.

Note: The property webapp-firewall-ruleset enables you to specify multiple values, with each value enclosed in quotes and separated by commas. For example:

```
webapp-firewall-ruleset="ruleset/vschola/*.conf", "/scratch/sababu/waf rules/rule2.conf"
```

To reset a property to its default value, do not provide a property value.

For example, property-name=<empty_string>

Example

```
tadm set-config-prop --user=admin --host=admin.example.com
--password-file=./admin.passwd --port=8989
--no-prompt --config=www.example.org user=otd_user
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [get-config-prop](#)

set-dns-cache-prop

Syntax

```
tadm set-dns-cache-prop common_options --config=config_name (property_name=property_value)+
```

Description

Use this command to set the Domain Name Server (DNS) cache properties.

Options

For information about *common_options*, run the [help](#) command.

--config|-c

Specify the name of the configuration to set the DNS cache properties.

Operands

property-name=property-value

Specify *name=value* pairs for one or more properties that you want to define. The *name=value* pairs should be separated by spaces.

You can set the following DNS cache properties:

enabled: Specifies whether the server should set DNS cache properties.

Values: *true*, *false*. Default: *true*.

max-age: Specifies the duration (in seconds) for which the entries must be kept in the cache.

Values: 1 to 31536000.

max-entries: Specifies the maximum number of DNS lookup results to write to the cache.

Values: 32 to 32768.

To reset a property to its default value, do not provide a property value.

For example, *property-name=<empty_string>*

Example

```
tadm set-dns-cache-prop --user=admin --host=admin.example.com
--password-file=./admin.passwd --port=8989
--no-prompt --config=www.example.org max-age=3848
max-entries=45
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [get-dns-cache-prop](#)

set-dns-prop

Syntax

```
tadm set-dns-prop common_options --config=config_name (property_name=property_value)+
```

Description

Use this command to set the Domain Name Server (DNS) lookup properties for a configuration.

Options

For information about *common_options*, run the [help](#) command.

--config|-c

Specify the name of the configuration to set the DNS properties.

Operands

property-name=property-value

Specify *name=value* pairs for one or more properties that you want to define. The *name=value* pairs should be separated by spaces.

You can set the following DNS properties:

enabled: Specifies whether the server should perform DNS lookups.

Values: *true*, *false*. Default: *false*.

async: Specifies whether the server uses its own asynchronous DNS resolver, instead of the Operating System's synchronous resolver.

Values: *true*, *false*. Default: *true*.

timeout: Specifies the duration (in seconds) after which the asynchronous DNS lookups should time out.

Values: 0.001 to 3600.

To reset a property to its default value, do not provide a property value.

For example, *property-name=<empty_string>*

Example

```
tadm set-dns-prop --user=admin --host=admin.example.com
--password-file=./admin.passwd --port=8989
--no-prompt --config=www.example.org timeout=34
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [get-dns-prop](#), [set-dns-cache-prop](#), [get-dns-cache-prop](#)

set-failover-group-primary

Syntax

```
tadm set-failover-group-primary common_options --config=config_name
--virtual-ip=ip --primary-node=node
```

Description

Use this command to toggle the primary and backup nodes in a failover group. If the administration node process is running as non-root on the node where the instances are located, then you must run [start-failover](#) on those nodes as a root user. This is to manually toggle the nodes. If this command is not executed, the nodes will not be toggled. And, when you execute [get-failover-group-prop](#), the result will show the configured primary and the backup nodes, which will not be the same as the runtime primary and backup nodes.

Options

For information about *common_options*, run the [help](#) command.

--config|-c

Specify the name of the configuration for which you want to toggle the primary and backup nodes of a failover group.

--virtual-ip|-i

Specify the virtual IP address of the failover group for which you want to toggle the primary and backup nodes.

--primary-node|-n

Specify the primary node for the failover group. This is the existing backup node of the failover group.

Example

```
tadm set-failover-group-primary --config=soa --virtual-ip=10.228.12.250
--primary-node=app2.example.com
```

```
tadm start-failover --user=admin
--password-file=./admin.passwd --host=admin.example.com --port=8989
--no-prompt --config=soa --instance-home=/home/otd
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [delete-failover-group](#), [create-failover-group](#), [list-failover-groups](#), [get-failover-group-prop](#), [start-failover](#), [stop-failover](#)

set-health-check-prop

Syntax

```
tadm set-health-check-prop common_options --config=config_name  
--origin-server-pool=origin_server_pool_name (property_name=property_value)+
```

Description

Use this command to set the health-check properties for an origin server pool.

Options

For information about `common_options`, run the [help](#) command.

`--config|-c`

Specify the configuration for which you want to set the health-check properties.

`--origin-server-pool|-o`

Specify the name of the origin-server pool for which you want to set the health-check properties.

Operands

`property-name=property-value`

Specify `name=value` pairs for one or more properties that you want to define. The `name=value` pairs should be separated by spaces.

You can set the following health-check properties:

`protocol`: Specifies the protocol for the health check requests.

Values: HTTP.

`interval`: Specifies the time interval (seconds) between two health check pings.

Values: Takes a positive integer. Default: 30.

`timeout`: Specifies the timeout value (seconds) for a ping connection or a request.

Values: Takes a positive integer. Default: 5.

`failover-threshold`: Specifies the number of consecutive failures for all requests sent to an origin server, after which the origin server should be marked as unavailable.

Values: Takes a positive integer. Maximum allowable value is 256. Default: 3.

`request-method`: Specifies the method that should be used for HTTP ping requests.

Values: GET or OPTIONS. Default: OPTIONS.

`request-uri`: Specifies the URI that should be used for HTTP health-check requests.

Values: URI String. Default: "/".

`response-code-match`: The response status codes that indicate a healthy origin server.

Values: A pipe-separated list of status codes. The status codes can be represented as modified regular expressions containing 3-character patterns. The first character can be either "x" or a number from 1 to 4. The second and third characters can be either "x" or a number from 0 to 9. For example, 200, 2xx|304, 1xx|2xx|3xx|4xx. This is applicable only when protocol is HTTP. For example, any 200 plus response code from the origin servers will be matched against 2xx (200=OK, 201=Created, 202=Accepted, 203=Non-Authoritative Information, 204=No Content, 205=Reset Content, and 206=Partial Content).

response-body-match: A regular expression that is used to match the HTTP response body to determine the origin server's health. This is applicable only when protocol is HTTP.

Values: Regular expression.

response-body-match-size: Specifies the maximum length of the response body that should match.

Values: Takes a positive integer. Default: 2048.

dynamic-server-discovery: Specifies if the server should dynamically discover Oracle WebLogic Server cluster nodes and add them to the pool.

Values: true, false. Default: false.

To reset a property to its default value, do not provide a property value.

For example, `property-name=<empty_string>`

Example

```
tadm set-health-check-prop --user=admin --host=admin.example.com
--password-file=./admin.passwd --port=8989 --no-prompt --config=www.example.org
--origin-server-pool=test-pool
failover-threshold=150 timeout=4
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [get-health-check-prop](#)

set-http-listener-prop

Syntax

```
tadm set-http-listener-prop common_options --config=config_name
--http-listener=name (property_name=property_value)+
```

Description

Use this command to set the HTTP listener properties.

Options

For information about `common_options`, run the [help](#) command.

`--config|-c`

Specify the name of the configuration to set the HTTP listener properties.

`--http-listener|-r`

Specify the name of the HTTP listener.

Operands

`property-name=property-value`

Specify `name=value` pairs for one or more properties that you want to define. The `name=value` pairs should be separated by spaces.

You can set the following HTTP listener properties:

`enabled`: Specifies whether the HTTP listener is enabled.

Values: `true`, `false`. Default: `true`.

`ip`: Specifies an IP address to listen.

Values: A valid IP address or an asterisk (*) to listen on all IP addresses.

`port`: Specifies the port to listen.

Values: A valid port number.

`acceptor-threads`: Specifies the number of threads dedicated for accepting connections received by this listener.

Values: 1 to 128.

Note: The property `acceptor-threads` can accept `default` as a value. Default implies that the server will compute the value of this property at runtime.

`server-name`: Specifies the default server name. Tells the server what to put in the host name section of any URLs it sends to the client. This affects URLs the server automatically generates; it doesn't affect the URLs for directories and files stored in the server. This name should be the alias name if your server uses an alias. If a colon and port number are appended, that port will be used in URLs that the server sends to the client.

Values: The value can include a scheme (for example, prefix `http://`) and port suffix (for example, `:80`).

blocking-io: Indicates whether the server uses the blocking I/O. If you specify this option, the HTTP listener socket is in the blocking mode.
Values: true, false. Default: false.

handle-protocol-mismatch: Indicates whether the server responds to SSL or non-SSL protocol mismatches in client requests. The default value is true, meaning the server will attempt to detect SSL or non-SSL protocol mismatches and send an HTTP redirect or SSL alert when a mismatch is detected.
Values: true, false. Default: true.

family: Specifies the socket family that is used to connect to the origin-server.
Values: inet, inet6, and inet-sdp. The values inet and inet6 represent IPV4 and IPV6 protocols respectively. The inet-sdp value is used for Sockets Direct Protocol (SDP). Default: inet.

Note: The property family can accept default as a value. Default implies that the server will compute the value of this property at runtime.

listen-queue-size: Specifies the size (in bytes) of the listen queue.
Values: 1 to 1048576.

receive-buffer-size: Specifies the size (in bytes) of the operating system socket receive buffer.
Values: 0 to 2147483647.

send-buffer-size: Specifies the size (in bytes) of the operating system socket send buffer.
Values: 0 to 2147483647.

default-virtual-server-name: Specifies the name of the virtual server that processes request that do not match a host.
Values: Takes a name value from the virtual server element.

description: Specifies the description of the HTTP listener.
Values: A text string.

To reset a property to its default value, do not provide a property value.
For example, `property-name=<empty_string>`

Example

```
tadm set-http-listener-prop --user=admin --host=admin.example.com
--password-file=./admin.passwd --port=8989
--no-prompt --config=www.example.org --http-listener=http_listen1
IP=192.19.1.10 port=1895
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-http-listener](#), [get-http-listener-prop](#), [list-http-listeners](#), [delete-http-listener](#)

set-http-prop

Syntax

```
tadm set-http-prop common_options --config=config_name (property_name=property_value)+
```

Description

Use this command to set the HTTP properties.

Options

For information about *common_options*, run the [help](#) command.

--config|-c

Specify the name of the configuration to set the HTTP properties.

Operands

property-name=property-value

Specify *name=value* pairs for one or more properties that you want to define. The *name=value* pairs should be separated by spaces.

You can set the following HTTP properties:

version: Specifies the highest HTTP protocol version the server supports.

Values: The default HTTP version string is HTTP/1.1

server-header: Specifies the server header information such as server software and version.

Values: The default server header is Oracle-Traffic-Director/11.1.1.6.0.

etag: Indicates if the server includes an Etag header field in its responses.

Values: true, false. Default: true.

request-header-buffer-size: Specifies the size (in bytes) of the buffer used to read HTTP request headers.

Values: 0 to 2147483647

strict-request-headers: Indicates whether the server rejects certain malformed HTTP request headers.

Values: true, false. Default: false.

max-request-headers: Specifies the maximum number of header fields in an HTTP request header.

Values: 1 to 512

output-buffer-size: Specifies the size (in bytes) of the buffer for HTTP responses.

Values: 0 to 2147483647

max-unchunk-size: Specifies the maximum size (in bytes) of a chunked HTTP request body that the server will unchunk.

Values: 0 to 2147483647

unchunk-timeout: Specifies the maximum time (in seconds) that the server waits for a chunked HTTP request body to arrive.

Values: 0 to 3600, or -1 for no timeout. Default: 60

`io-timeout`: Specifies the maximum time (in seconds) that the server waits for an individual packet.

Values: 0 to 3600, or -1 for no timeout.

`request-body-timeout`: Specifies the maximum time (in seconds) that the server waits for a complete HTTP request body.

Values: 0 to 604800, or -1 for no timeout.

`request-header-timeout`: Specifies the maximum time (in seconds) that the server waits for a complete HTTP request header.

Values: 0 to 604800, or -1 for no timeout. Default: 30.

`ecid`: Specifies whether the server generates, propagates, and logs the execution context. The value of the ECID is a unique identifier that can be used to correlate individual events as being part of the same request execution flow.

For example, events that are identified as being related to a particular request typically have the same ECID value. However, the format of the ECID string itself is determined by an internal mechanism that is subject to change; therefore, you should not have or place any dependencies on that format.

Values: `true`, `false`. Default: `true`

`websocket-strict-upgrade`: Enables/disables strict adherence to RFC 6455 during a websocket upgrade request. When `websocket-strict-upgrade` is `true`, additional rules are checked, as prescribed by the RFC 6455, to ensure that only clients that adhere strictly to RFC 6455 are allowed.

Values: `true`, `false`. Default: `false`.

To reset a property to its default value, do not provide a property value.

For example, `property-name=<empty_string>`

Example

```
tadm set-http-prop --user=admin --host=admin.example.com
--password-file=./admin.passwd --port=8989
--no-prompt --config=www.example.org
server-header=OTD-server-header request-header-buffer-size=278
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [get-http-prop](#)

set-keep-alive-prop

Syntax

```
tadm set-keep-alive-prop common_options --config=config_name (property_name=property_value)+
```

Description

Use this command to set keep-alive subsystem properties.

Options

For information about *common_options*, run the [help](#) command.

--config|-c

Specify the name of the configuration to set keep-alive properties.

Operands

property-name=property-value

Specify *name=value* pairs for one or more properties that you want to define. The *name=value* pairs should be separated by spaces.

You can set the following keep-alive properties:

enabled: Specifies whether the keep-alive subsystem is enabled.

Values: *true*, *false*. Default: *true*.

threads: Specifies the number of keep-alive subsystem threads.

Values: 1 to 128. Default: 1.

Note: The property *threads* can accept *default* as a value. Default implies that the server will compute the value of this property at runtime.

max-connections: Specifies the maximum number of concurrent keep-alive connections that the server supports.

Values: 1 to 1048576. Default: 200.

Note: The property *max-connections* can accept *default* as a value. Default implies that the server will compute the value of this property at runtime.

timeout: Specifies the timeout (in seconds) after which an inactive keep-alive connection can be used.

Values: 0.001 to 3600. Default: 30 seconds.

poll-interval: Specifies the interval (in seconds) between polls.

Values: 0.001 to 1. Default: .001 seconds.

To reset a property to its default value, do not provide a property value.

For example, *property-name=<empty_string>*

Example

```
tadm set-keep-alive-prop --user=admin --host=admin.example.com
--password-file=./admin.passwd --port=8989
--no-prompt --config=www.example.org poll-interval=1 timeout=25
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [get-keep-alive-prop](#)

set-localization-prop

Syntax

```
tadm set-localization-prop common_options [--vs=vs_name] --config=config_name
(property_name=property_value)+
```

Description

Use this command to set the localization properties.

Options

For information about *common_options*, run the [help](#) command.

--vs|-s

Specify the name of the virtual server.

--config|-c

Specify the name of the configuration to set the localization properties.

Operands

property-name=property-value

Specify *name=value* pairs for one or more properties that you want to define. The *name=value* pairs should be separated by spaces.

You can set the following localization properties:

default-language: The default language with which the messages and content are displayed.

Values: User specified language codes. Default: en.

negotiate-client-language: Specifies whether the server uses the *accept-language* HTTP header to negotiate the content language with clients.

Values: true, false. Default: false.

To reset a property to its default value, do not provide a property value.

For example, *property-name=<empty_string>*

Example

```
tadm set-localization-prop --user=admin --host=admin.example.com
--password-file=./admin.passwd --port=8989 --no-prompt --config=www.example.org
negotiate-client-language=false
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [get-localization-prop](#)

set-log-prop

Syntax

```
tadm set-log-prop common_options --config=config_name (property_name=property_value)+
```

Description

Use this command to set the log properties.

Options

For information about `common_options`, run the [help](#) command.

`--config|-c`

Specify the name of the configuration to set the log properties.

Operands

`property-name=property-value`

Specify name=value pairs for one or more properties that you want to define. The name=value pairs should be separated by spaces.

You can set the following log properties:

`log-stdout`: Specifies whether the server logs data that applications write to stdout.

Values: true, false. Default: true.

`log-stderr`: Specifies whether the server logs data that applications write to stderr.

Values: true, false. Default: true.

`log-virtual-server-name`: Specifies whether the server includes the virtual server name in log messages.

Values: true, false. Default: true.

`log-to-console`: Specifies whether the server writes log messages to the console.

Values: true, false. Default: true.

`log-to-syslog`: Specifies whether the server writes log messages to syslog.

Values: true, false. Default: false.

`date-format`: Specifies the date format for the log message time stamps.

Values: Default value: %d/%b/%Y:%H:%M:%S

`archive-suffix`: Specifies the suffix appended to the log file names.

Values: Default value: %Y%m%d%H%M

`archive-command`: This is executed after the server rotates a log file.

Values: A program command line, for example: gzip

`log-level`: Specifies the log verbosity for the server as a whole.

Values: INCIDENT_ERROR:1, ERROR:1, ERROR:16, ERROR:32, WARNING:1, TRACE:1, TRACE:16, TRACE:32. Default: NOTIFICATION:1.

`log-file`: Specifies the name and location of the log file.

Values: User defined name and location. Default: ../logs/server.log

To reset a property to its default value, do not provide a property value.
For example, `property-name=<empty_string>`

Example

```
tadm set-log-prop --user=admin --password-file=./admin.passwd  
--host=admin.example.com --port=8989 --no-prompt --config=www.example.org  
log-level=error:1
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [get-log-prop](#), [get-log](#)

set-origin-server-pool-prop

Syntax

```
tadm set-origin-server-pool-prop common_options --config=config_name  
--origin-server-pool=origin_server_pool_name (property_name=property_value)+
```

Description

Use this command to set the origin-server pool properties.

Options

For information about `common_options`, run the [help](#) command.

`--config|-c`

Specify the name of the configuration for which you want to set the origin-server pool properties.

`--origin-server-pool|-o`

Specify the name of the origin-server pool for which you want to set the properties.

Operands

`property-name=property-value`

Specify `name=value` pairs for one or more properties that you want to define. The `name=value` pairs should be separated by spaces.

You can set the following origin-server pool properties:

family: Specifies the socket family that is used to connect to the origin-server. Values: `inet`, `inet6`, and `inet-sdp`. The values `inet` and `inet6` represent IPV4 and IPV6 protocols respectively. The `inet-sdp` value is used for Sockets Direct Protocol (SDP). Default: `inet`.

load-distribution: The load-balancing method that should be used for distributing requests to the origin-server pool.

Values: `least-connection-count`, `least response time` and `round-robin`. Default: `least-connection-count`

To reset a property to its default value, do not provide a property value. For example, `property-name=<empty_string>`

Example

```
tadm set-origin-server-pool-prop --user=admin --host=admin.example.com  
--password-file=./admin.passwd --port=8989  
--no-prompt --config=www.example.org  
--origin-server-pool=test-pool family=inet  
load-distribution=round-robin
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [get-origin-server-pool-prop](#), [list-origin-server-pools](#), [delete-origin-server-pool](#),
[create-origin-server-pool](#)

set-origin-server-prop

Syntax

```
tadm set-origin-server-prop common_options --config=config_name
--origin-server-pool=origin_server_pool_name --origin-server=host:port (property_
name=property_value)+
```

Description

Use this command to set the properties of an origin-server.

Options

For information about `common_options`, run the [help](#) command.

`--config|-c`

Specify the configuration for which you want to set origin-server properties.

`--origin-server-pool|-o`

Specify the name of the origin-server pool for which you want to set the origin-server properties.

`--origin-server|-O`

Specify an origin server in the format `host:port`

Operands

`property-name=property-value`

Specify `name=value` pairs for one or more properties that you want to define. The `name=value` pairs should be separated by spaces.

You can set the following origin server properties:

enabled: Specifies whether the requests can be routed to this origin server.

Values: `true`, `false`. Default: `true`.

host: Specifies the host name or the IP address of the origin server.

Values: String.

port: Specifies the port number of the origin server.

Values: Integer. 80 is the default port if the origin server pool type is HTTP. 443 is the default port if the origin server pool type is HTTPS.

weight: Specifies the load distribution weight for the origin server.

Values: 0 to 1000. Default: 1.

backup: Specifies whether the origin sever is a backup server. Requests will be sent to the backup origin server only when none of the primary (non-backup) origin servers is available.

Values: `true`, `false`. Default: `false`.

max-connections: Specifies the maximum number of concurrent connections to the server.

Values: 0 or a positive integer. Maximum allowable value is 20480. Default: 0.

ramp-up-time: The time (in seconds) that Oracle Traffic Director should take to ramp up the request sending rate to the full capacity of this origin server.

Values: Positive integer. If `max-connections` is set to 0, `ramp-up-time` is ignored.

To reset a property to its default value, do not provide a property value.
For example, `property-name=<empty_string>`

Example

```
tadm set-origin-server-prop --user=admin --host=admin.example.com
--password-file=./admin.passwd --port=8989
--no-prompt --config=www.example.org --origin-server-pool=test-pool
--origin-server=www.email.com:8080 weight=998 max-connections=234
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [get-origin-server-prop](#), [list-origin-servers](#), [delete-origin-server](#),
[create-origin-server](#)

set-pkcs11-prop

Syntax

```
tadm set-pkcs11-prop common_options --config=config_name (property_name=property_value)+
```

Description

Use this command to set the PKCS#11 properties. Oracle Traffic Director introduces an option to instruct Network Security Services (NSS) to bypass the PKCS#11 layer during parts of the SSL/TLS processing. Bypassing the PKCS#11 layer improves performance.

Options

For information about *common_options*, run the [help](#) command.

`--config|-c`

Specify the name of the configuration to set the PKCS#11 properties.

Operands

`property-name=property-value`

Specify `name=value` pairs for one or more properties that you want to define. The `name=value` pairs should be separated by spaces.

You can set the following PKCS#11 properties:

`enabled`: Specifies whether the server initializes PKCS#11 tokens, prompting for personal identification numbers (PINs) as necessary.

Values: Default is `true` if SSL is enabled and `false` if SSL is disabled.

`crl-path`: Specifies the directory that contains dynamically updated CRL files.

Values: Name of the directory. If a relative path is used, it is relative to the server's `config` directory.

`allow-bypass`: If enabled, the PKCS#11 layer is bypassed during parts of the SSL/TLS processing. Bypassing the PKCS#11 layer enhances performance.

Values: `true`, `false`. Default: `true`.

To reset a property to its default value, do not provide a property value.

For example, `property-name=<empty_string>`

Example

```
tadm set-pkcs11-prop --user=admin --host=admin.example.com
--password-file=./admin.passwd --port=8989
--no-prompt --config=www.example.org enabled=false
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [get-pkcs11-prop](#), [list-tokens](#), [set-token-prop](#), [set-token-pin](#)

set-qos-limits-prop

Syntax

```
tadm set-qos-limits-prop common_options --config=config_name --vs=vs_name  
(property_name=property_value)+
```

Description

Use this command to set the quality of service (QoS) limit properties for a virtual server. Quality of Service refers to the performance limits that you set for a server instance or virtual server. You can limit two areas: the amount of bandwidth and the number of connections.

Options

For information about *common_options*, run the [help](#) command.

--config|-c

Specify the name of the configuration to set the QoS limits properties.

--vs|-s

Specify the name of the virtual server.

Operands

property-name=property-value

Specify *name=value* pairs for one or more properties that you want to define. The *name=value* pairs should be separated by spaces.

You can set the following qos limits properties:

enabled: Specifies whether the qos limits is enforced during the runtime.

Values: *true*, *false*. Default: *true*.

max-bps: Specifies the maximum transfer rate (bytes/second).

Values: 1 to 2147483647. No default value.

max-connections: Specifies the maximum number of concurrent connections.

Values: 1 to 1048576

To reset a property to its default value, do not provide a property value.

For example, *property-name=<empty_string>*

Example

```
tadm set-qos-limits-prop --user=admin --host=admin.example.com  
--password-file=./admin.passwd --port=8989  
--no-prompt --config=www.example.org  
--vs=soa.example.org max-bps=3373 max-connections=44838
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [get-qos-limits-prop](#), [get-qos-prop](#), [set-qos-prop](#)

set-qos-prop

Syntax

```
tadm set-qos-prop common_options --config=config_name (property_name=property_value)+
```

Description

Use this command to set the quality of service (QoS) settings for a configuration.

Options

For information about `common_options`, run the [help](#) command.

`--config|-c`

Specify the name of the configuration to set QoS properties.

Operands

`property-name=property-value`

Specify `name=value` pairs for one or more properties that you want to define. The `name=value` pairs should be separated by spaces.

You can set the following qos properties:

`enabled`: Specifies whether the QoS settings are enabled.

Values: `true`, `false`. Default: `true`.

`interval`: Specifies the interval (in seconds), over which QoS information is averaged.

Values: 0.001 to 3600.

To reset a property to its default value, do not provide a property value.

For example, `property-name=<empty_string>`

Example

```
tadm set-qos-prop --user=admin --host=admin.example.com  
--password-file=./admin.passwd --port=8989  
--no-prompt --config=www.example.org interval=0.005
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [get-qos-prop](#), [get-qos-limits-prop](#), [set-qos-limits-prop](#)

set-request-limit-prop

Syntax

```
tadm set-request-limit-prop common_options --config=config_name
--vs=vs_name --request-limit=request_limit_name (property_name=property_value)+
```

Description

Use this command to set the request limit properties for a virtual-server.

Options

For information about *common_options*, run the [help](#) command.

--config|-c

Specify the name of the configuration to set the request-limit properties.

--vs|-s

Specify the name of the virtual server.

--request-limit|-l

Specify the name for request limit properties.

Operands

property-name=property-value

Specify name=value pairs for one or more properties that you want to define. The name=value pairs should be separated by spaces.

You can set the following request-limit properties:

max-rps: Specifies the maximum number of requests that the virtual server can receive per second.

Values: 0 to 999999999.

max-connections: Specifies the maximum number of concurrent matching connections.

Values: 0 to 999999999.

continue-condition: Determines the condition for a blocked request type to become available again.

Values: *silence* and *threshold*. Default: *threshold*.

error-code: Specifies the HTTP status code to return for blocked requests.

Values: Default value: 503

monitor-attribute: Specifies a request attribute to monitor.

Values: Any valid string. For example, *jpeg*: *\$ip*.

rps-compute-interval: Specifies the time interval (in seconds) in which the average RPS (request per second) is computed.

Values: Default value: 30

To reset a property to its default value, do not provide a property value.

For example, *property-name=<empty_string>*

Example

```
tadm set-request-limit-prop --user=admin --host=admin.example.com
--password-file=./admin.passwd --port=8989
--no-prompt --config=www.example.org --vs=soa.example.org
--request-limit=rule-request-limit-1 max-rps=2999 max-connections=333999
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [get-request-limit-prop](#), [list-request-limits](#), [delete-request-limit](#),
[create-request-limit](#)

set-route-prop

Syntax

```
tadm set-route-prop common_options --config=config-name --vs=vs_name
--route=route_name (property_name=property_value)+
```

Description

Use this command to set the route properties for a virtual server.

Options

For information about `common_options`, run the [help](#) command.

`--config|-c`

Specify the name of the configuration to set the route properties.

`--vs|-s`

Specify the name of the virtual server.

`--route|-r`

Specify the name for route properties.

Operands

`property-name=property-value`

Specify name=value pairs for one or more properties that you want to define. The name=value pairs should be separated by spaces.

You can set the following route properties:

`server`: Specifies the server name.

Values: Must be a text string.

`sticky-cookie`: Specify the name of the cookie that causes subsequent requests to stick to a particular origin server.

Values: Must be a text string.

`sticky-uri-param`: Specify the name of a URI parameter to inspect for route information. When the URI parameter is present in a request URI and its value contains a colon (:), followed by a route ID, the request will 'stick' to the origin server identified by that route ID.

Values: Must be a text string.

`route-header`: Specify the name of the HTTP request header that is used to communicate route IDs to the origin servers.

Values: Must be a text string.

`route-cookie`: Specify the name of the cookie generated by the server when it encounters a `sticky-cookie` cookie in a response. The `route-cookie` parameter stores the route ID that enables the server to direct subsequent requests back to the same origin server.

Values: Must be a text string.

`rewrite-headers`: Specify a list of HTTP request headers separated by commas.

Values: Must be a text string.

Note: The property `rewrite-headers` enables you to specify multiple values, with each value enclosed in quotes and separated by commas.

`validate-server-cert`: Specify whether the server validates the certificate presented by the origin servers.

Values: `true`, `false`. Default: `true`.

`use-keep-alive`: Specifies whether the HTTP client can use existing persistent connections for all types of requests.

Values: `true`, `false`. Default: `true`.

`keep-alive-timeout`: Specifies the maximum number (in seconds) to retain persistent connectivity.

Values: Integer. Default: 29

`timeout`: Specifies the maximum number (in seconds) that a connection can be in a idle state.

Values: Integer. Default: 300

`always-use-keep-alive`: Specifies whether the HTTP client can reuse existing connections for all types of requests.

Values: `true`, `false`. Default: `false`.

`protocol`: Specifies the HTTP protocol version string.

Values: Must be in a text string.

`proxy-agent`: Specify whether the proxy server product name and version has to be forwarded to the origin servers.

Values: `true`, `false`. Default: `true`.

`origin-server-pool`: Specify the pool of origin servers of the type HTTP for this route.

Values: HTTP.

`websocket-upgrade-enabled`: Specify whether standard HTTP(S) connections should be upgraded to bi-directional, full-duplex WebSocket connections.

Values: `true`, `false`. Default: `true`.

`websocket-idle-timeout`: The maximum number of seconds a connection can be idle.

Values: Integer (If no value is specified, then the timeout from the TCP connection thread pool (300 seconds) is used).

`from`: Specify the URI prefix to map. The prefix must not contain trailing slashes.

`to`: Specify the URL prefix to which the request should be mapped. The prefix must not contain trailing slashes.

`buffer-size`: The size (in bytes) of individual access log buffers.

Values: 0 to 2147483647.

To reset a property to its default value, do not provide a property value.

For example, `property-name=<empty_string>`

Example

```
tadm set-route-prop --user=admin --host=admin.example.com
--password-file=./admin.passwd --port=8989
```

```
--no-prompt --config=www.example.org  
--vs=soa.example.org --route=route-1 keep-alive-timeout=29 from=/ to=/docs
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [get-route-prop](#), [list-proxy-info](#), [forward-proxy-info](#), [block-proxy-info](#), [list-routes](#), [delete-route](#), [create-route](#)

set-snmp-prop

Syntax

```
tadm set-snmp-prop common_options --config=config_name (property_name=property_value)+
```

Description

Use this command to enable and define settings for the SNMP subagents.

Options

For information about `common_options`, run the [help](#) command.

`--config|-c`

Specify the name of the configuration to set the SNMP properties.

Operands

`property-name=property-value`

Specify name=value pairs for one or more properties that you want to define. The name=value pairs should be separated by spaces.

You can set the following SNMP properties:

`enabled`: Specifies whether the SNMP agent is enabled. If enabled, the SNMP subagent gathers information about the server and passes the information to the master agent.

Values: `true`, `false`. Default: `true`.

`description`: Specifies the description of the server.

Values: Must be in a text string.

`organization`: Specifies the name of the organization responsible for the server.

Values: Must be in a text string.

`location`: Specifies the location of the server.

Values: Must be in a text string.

`contact`: Specifies the contact information of the person responsible for the server.

Values: Must be in a text string.

To reset a property to its default value, do not provide a property value.

For example, `property-name=<empty_string>`

Example

```
tadm set-snmp-prop --config=www.example.org description=This is snmp test
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [get-snmp-prop](#), [start-snmp-subagent](#), [stop-snmp-subagent](#)

set-ssl-prop

Syntax

```
tadm set-ssl-prop common_options --config=config_name  
(--http-listener=name|--tcp-listener=name) (property_name=property_value)+
```

Description

Use this command to set the SSL properties for a listener. SSL is a software library establishing a secure connection between the client and server. SSL is used to implement HTTPS, the secure version of HTTP.

Options

For information about `common_options`, run the [help](#) command.

`--config|-c`

Specify the name of the configuration to set SSL properties.

`--http-listener|-r`

Specify the name of the HTTP listener.

`--tcp-listener|-t`

Specify the name of the TCP listener.

Operands

`property-name=property-value`

Specify `name=value` pairs for one or more properties that you want to define. The `name=value` pairs should be separated by spaces.

You can set the following HTTP properties:

`enabled`: Specifies whether SSL support is enabled for the listener.

Values: `true`, `false`. Default: `true`.

`strict-sni-vs-host-match`: Specifies that if the value is `false`, the default certificate is sent to clients which do not support SNI (Server Name Indication) extension.

Values: `true`, `false`. Default: `false`.

`tls-session-tickets-enabled`: Specifies whether TLS session Ticket Extension feature is enabled.

Values: `true`, `false`. Default: `true`.

`server-cert-nickname`: Specifies the nickname of the certificate that the server presents to the clients.

Values: zero or one for RSA and zero or one for ECC.

Note: The property `server-cert-nickname` enables you to specify multiple values, with each value enclosed in quotes and separated by commas.

`ssl3`: Specifies whether SSL3 connections are accepted.

Values: `true`, `false`. Default: `true`.

`tls`: Specifies whether TLS connections are accepted.

Values: `true`, `false`. Default: `true`.

`client-auth`: Specifies the method of client certificate authentication.

Values: `required`, `optional`, or `false`. When you choose `required` option, the server requests the client for a certificate; if the client does not provide a certificate, the connection is closed. When you choose `optional` option, the server requests the client for a certificate, but does not require it. The connection is established even if the client does not provide a certificate. Default: `false`. The client authentication is disabled by default.

`client-auth-timeout`: Indicates the duration (in seconds) after which a client authentication handshake fails.

Values: 0.001 to 3600.

`max-client-auth-data`: Specifies the number of characters of authentication data that the server can buffer.

Values: 0 to 2147483647.

To reset a property to its default value, do not provide a property value.

For example, `property-name=<empty_string>`

Example

```
tadm set-ssl-prop --user=admin --host=admin.example.com
--password-file=./admin.passwd --port=8989
--no-prompt --config=www.example.org --http-listener=config1_ls
max-client-auth-data=18976 client-auth-timeout=200
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [get-ssl-prop](#)

set-ssl-session-cache-prop

Syntax

```
tadm set-ssl-session-cache-prop common_options --config=config_name (property_name=property_value)+
```

Description

Use this command to set the SSL session cache properties.

Options

For information about `common_options`, run the [help](#) command.

`--config|-c`

Specify the name of the configuration to set the SSL session cache properties.

Operands

`property-name=property-value`

Specify `name=value` pairs for one or more properties that you want to define. The `name=value` pairs should be separated by spaces.

You can set the following SSL session cache properties:

`enabled`: Specifies whether the server writes SSL/TLS sessions to the cache.

Values: `true`, `false`. Default: `true`.

`max-entries`: Specifies the maximum number of SSL/TLS sessions that are written to the cache by the server.

Values: 1 to 524288.

`max-ssl3-tls-session-age`: Specifies the maximum amount of time (in seconds) a SSL/TLS session is written to the cache.

Values: 5 to 86400.

To reset a property to its default value, do not provide a property value.

For example, `property-name=<empty_string>`

Example

```
tadm set-ssl-session-cache-prop --user=admin  
--password-file=./admin.passwd --host=admin.example.com  
--port=8989 --no-prompt --config=www.example.org max-entries=12876  
max-ssl3-tls-session-age=789
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [get-ssl-session-cache-prop](#)

set-stats-prop

Syntax

```
tadm set-stats-prop common_options --config=config_name (property_name=property_value)+
```

Description

Use this command to set the properties of the statistics collection subsystem.

Options

For information about `common_options`, run the [help](#) command.

`--config|-c`

Specify the name of the configuration for which you want to set properties of the statistics collection subsystem.

Operands

`property-name=property-value`

Specify `name=value` pairs for one or more properties that you want to define. The `name=value` pairs should be separated by spaces.

You can set the following statistics properties:

`enabled`: Specifies whether the server collects the statistics.

Values: `true`, `false`. Default: `true`.

`interval`: Specifies the interval (in seconds) at which the statistics are updated.

Values: 0.001 to 3600.

`profiling`: Specifies whether the performance buckets used to track NSAPI function execution time are enabled at runtime.

Values: `true`, `false`. Default: `true`.

To reset a property to its default value, do not provide a property value.

For example, `property-name=<empty_string>`

Example

```
tadm set-stats-prop --user=admin --host=admin.example.com
--password-file=./admin.passwd --port=8989
--no-prompt --config=www.example.org interval=0.005
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [get-stats-prop](#)

set-tcp-listener-prop

Syntax

```
tadm set-tcp-listener-prop common_options --config=config_name --tcp-listener=name
(property_name=property_value)+
```

Description

Use this command to set the TCP listener properties.

Options

For information about *common_options*, run the [help](#) command.

--config|-c

Specify the name of the configuration for which you want to set properties of the TCP listener.

--tcp-listener|-t

Specify the name of the TCP listener.

Operands

property-name=property-value

Specify *name=value* pairs for one or more properties that you want to define. The *name=value* pairs should be separated by spaces.

You can set the following *tcp-listener* properties:

enabled: Specifies whether the instance is enabled.

Values: true, false. Default: true.

name: Specifies the name of the TCP listener.

Values: Must be in a text string.

ip: Specify the Internet Protocol (IP) address for the TCP listener.

Values: A valid IP address or an asterisk (*) to listen on all IP addresses.

family: Specify the internet protocol family, for example: `IPv4`, and `IPv6`. The default is `IPv4` (`family=inet`). To use the IPv6 address, specify `family=inet6`.

Note: The property *family* can accept `default` as a value. Default implies that the server will compute the value of this property at runtime.

acceptor-threads: Specifies the number of threads dedicated to accept connections received by this listener.

Values: 1 to 128. Default: 1 per CPU.

Note: The property *acceptor-threads* can accept `default` as a value. Default implies that the server will compute the value of this property at runtime.

`tcp-proxy-name`: Specifies the name of the TCP proxy.

Values: Must be in a text string.

`listen-queue-size`: Specifies the size (in bytes) of the listen queue.

Values: 0 to 65536.

`receive-buffer-size`: Specifies the size (in bytes) of the operating system socket receive buffer.

Values: 1 to 1048576.

`send-buffer-size`: Specifies the size (in bytes) of the operating system socket send buffer.

Values: 1 to 1048576.

`description`: Specifies the description of the TCP listener.

Values: Must be in a text string.

To reset a property to its default value, do not provide a property value.

For example, `property-name=<empty_string>`

Example

```
tadm set-tcp-listeners-prop --user=admin
--password-file=./admin.passwd --port=8989
--config=www.example.org --tcp-listener=TCP_Listener1 listen-queue-size=238
max-threads=789
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-tcp-listener](#), [delete-tcp-listener](#), [list-tcp-listeners](#), [get-tcp-listener-prop](#)

set-tcp-proxy-prop

Syntax

```
tadm set-tcp-proxy-prop common_options --config=config_name --tcp-proxy=tcp_proxy_name (property_name=property_value)+
```

Description

Use this command to set the properties of the TCP proxy for a configuration.

Options

For information about *common_options*, run the [help](#) command.

--config|-c

Specify the name of the configuration for which you want to set the properties of the TCP proxy.

--tcp-proxy|-r

Specify the name of the TCP proxy.

Operands

property-name=property-value

Specify *name=value* pairs for one or more properties that you want to define. The *name=value* pairs should be separated by spaces.

You can set the following tcp-proxy properties:

enabled: Specifies whether the TCP listener instance is enabled.

Values: true, false. Default: true.

name: Specifies the name of the TCP listener.

Values:

session-idle-timeout: Specifies the maximum timeout (in seconds) for load balancer to wait for receiving/sending data for a session.

Values: Number. Default: 300 seconds.

origin-server-pool-name: Specifies the name of the origin-server pool.

Values: Text.

To reset a property to its default value, do not provide a property value.

For example, *property-name=<empty_string>*

Example

```
tadm set-tcp-proxy-prop --user=admin --host=admin.example.com
--password-file=./admin.passwd --port=8989
--no-prompt --tcp-proxy=proxy1 --config=www.example.org
access-log-file=./logs/www_example_com_access.log
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-tcp-proxy](#), [delete-tcp-proxy](#), [list-tcp-proxies](#), [get-tcp-proxy-prop](#)

set-tcp-thread-pool-prop

Syntax

```
tadm set-tcp-thread-pool-prop common_options --config=config_name (property_name=property_value)+
```

Description

Use this command to set the thread-pool properties of a configuration. The `tcp-thread-pool` element configures the threads used to proxy data for upgraded websocket connections and generic TCP connections. You can use TCP thread pools to allocate a certain number of threads to a specific service. By defining a pool with the maximum number of threads as 1, only one request is allowed to the specified service function.

Options

For information about `common_options`, run the [help](#) command.

Operands

`property-name=property-value`

Specify the name of the property that you want to view (Optional).

You can view the following `tcp-thread-pool` properties:

`enabled`: Specifies whether the virtual server is enabled.

Values: `true`, `false`. Default: `true`.

`threads`: Specifies the number of threads in the proxy thread pool.

Values: 1 to 512.

Note: The property `threads` can accept `default` as a value. Default implies that the server will compute the value of this property at runtime.

`max-connections`: Specifies the number of concurrent connections to the server.

Values: 1 to 1048576.

Note: The property `max-connections` can accept `default` as a value. Default implies that the server will compute the value of this property at runtime.

`timeout`: Specifies the maximum number (in seconds) that a connection can be in a idle state. This value will be overridden by TCP or websocket subsystem.

Values: .001 to 3600. Default: 300 seconds.

`stack-size`: Specifies the stack size (in bytes) for TCP request processing threads.

Values: 8192 to 67108864 or 0. Default 32768.

`poll-interval`: Specifies the interval (in seconds) between polls.

Values: 0.001 to 1. Default 0.010 seconds.

`buffer-size`: Specifies the buffer size (in bytes) for TCP request processing threads. Values: 0 to 1048576 or 0. Default 16384.

Example

```
tadm set-tcp-thread-pool-prop
--config=www.example.org enabled buffer-size=100
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [get-tcp-thread-pool-prop](#)

set-thread-pool-prop

Syntax

```
tadm set-thread-pool-prop common_options --config=config_name (property_name=property_value)+
```

Description

Use this command to set the thread-pool properties for a configuration. The `thread-pool` element configures the threads used to process HTTP requests. You can use thread pools to allocate a certain number of threads to a specific service. By defining a pool with the maximum number of threads as 1, only one request is allowed to the specified service function.

Options

For information about `common_options`, run the [help](#) command.

```
--config|-c
```

Specify the name of the configuration for which you want to set thread-pool properties.

Operands

```
property-name=property-value
```

Specify `name=value` pairs for one or more properties that you want to define. The `name=value` pairs should be separated by spaces.

You can set the following thread-pool properties:

`queue-size`: Specifies the maximum number of concurrent HTTP connections that can be queued for processing.

Values: 1 to 1048576.

Note: The property `queue-size` can accept `default` as a value. Default implies that the server will compute the value of this property at runtime.

`min-threads`: Specifies the minimum number of HTTP request processing threads. Values: 1 to 4096.

Note: The property `min-threads` can accept `default` as a value. Default implies that the server will compute the value of this property at runtime.

`max-threads`: Specifies the maximum number of HTTP request processing threads. Values: 1 to 4096.

Note: The property `max-threads` can accept `default` as a value. Default implies that the server will compute the value of this property at runtime.

`stack-size`: Specifies the stack size (in bytes) for HTTP request processing threads. Values: 8192 to 67108864.

To reset a property to its default value, do not provide a property value. For example, `property-name=<empty_string>`

Example

```
tadm set-thread-pool-prop --user=admin --host=admin.example.com
--password-file=./admin.passwd --port=8989
--no-prompt --config=www.example.org queue-size=238 max-threads=789
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [get-thread-pool-prop](#)

set-token-pin

Syntax

```
tadm set-token-pin common_options [--save-pin=true/false] --token=name  
--config=config_name
```

Description

Use this command to set or reset the SSL token pin for the server.

Options

For information about *common_options*, run the [help](#) command.

--save-pin|-a

If you specify this option, the SSL token PIN gets saved in *server.xml* file.

--token|-t

Specify the name of the PKCS #11 token.

--config|-c

Specify the name of the configuration to set the token pin.

Example

```
tadm set-token-pin --user=admin --password-file=./admin.passwd  
--host=admin.example.com --port=8989 --no-prompt  
--token=internal --config=www.example.org  
<tadm Enter token-pin:  
<tadm Enter new token-pin:  
<tadm Enter new-token-pin again:
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [get-pkcs11-prop](#), [set-pkcs11-prop](#), [list-tokens](#), [set-token-prop](#)

set-token-prop

Syntax

```
tadm set-token-prop common_options --config=config_name --token=name
([--set-password] | (property_name=property_value)*)
```

Description

Use this command to enable or disable the SSL tokens for the server. You can also use this command to save the token pin in the `server.xml` file, which will facilitate unsupervised server startup.

Options

For information about `common_options`, run the [help](#) command.

`--config|-c`

Specify the name of the configuration to set the token properties.

`--token|-t`

Specify the name of the PKCS #11 token that contains the certificates.

`--set-password|-r`

If you specify this option, it can only be saved in `server.xml` file if there is already a (Personal Identification Number) PIN set on the token.

To reset a property to its default value, do not provide a property value.

For example, `property-name=<empty_string>`

Operands

`property-name=property-value`

Specify `name=value` pairs for one or more properties that you want to define. The `name=value` pairs should be separated by spaces.

You can set the following token property:

enabled: Specifies whether the server initializes this token, prompting for a personal identification number (PIN) if necessary.

Values: `true`, `false`. Default: `true`.

Example

```
tadm set-token-prop --user=admin --password-file=../admin.pwd
--host=admin.example.com --port=8989 --config=www.example.org --token=internal
enabled=true
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [get-pkcs11-prop](#), [set-pkcs11-prop](#), [list-tokens](#), [set-token-pin](#)

set-virtual-server-prop

Syntax

```
tadm set-virtual-server-prop common_options --config=config_name
--vs=vs_name (property_name=property_value)+
```

Description

Use this command to set the properties of a virtual-server.

Options

For information about `common_options`, run the [help](#) command.

`--config|-c`

Specify the name of the configuration to set the virtual-server properties.

`--vs|-s`

Specify the name of the virtual server.

Operands

`property-name=property-value`

Specify `name=value` pairs for one or more properties that you want to define. The `name=value` pairs should be separated by spaces.

You can set the following virtual-server properties:

`enabled`: Specifies whether the virtual server is enabled.

Values: `true`, `false`. Default: `true`.

`host`: Indicates the host name of the virtual-server services.

Values: The value can be a host name or a wild card.

Note: The property `host` enables you to specify multiple values, with each value enclosed in quotes and separated by commas.

`default-object-name`: Specifies the name of the root (`obj.conf`) object.

Values: Default value: `default`.

Note: The property `default-object-name` can accept `default` as a value. Default implies that the server will compute the value of this property at runtime.

`http-listener-name`: The name of a HTTP listener associated with one or more of the virtual server's host name.

Values: One of the names from `http-listener` element.

Note: The property `http-listener-name` enables you to specify multiple values, with each value enclosed in quotes and separated by commas.

`object-file`: Specifies the `obj.conf` file that controls request processing for virtual-servers.

Values: Default value: `config_name-obj.conf`, and the user can specify any valid file.

`canonical-server-name`: The canonical name of the virtual server.

Values: The value could be a host name or a URL prefix

`log-file`: Specifies the log file for the virtual server.

Values: The value is the log file name, for example `../logs/errors.log`

`server-cert-nickname`: Specifies the nickname of the certificate that the server presents to the clients.

Values: zero or one for RSA and zero or one for ECC.

Note: The property `server-cert-nickname` enables you to specify multiple values, with each value enclosed in quotes and separated by commas.

`webapp-firewall-ruleset`: Specifies the location where the Web Application Firewall (WAF) ruleset files are stored.

Values: Any valid directory where WAF ruleset files are stored.

Note: The property `webapp-firewall-ruleset` enables you to specify multiple values, with each value enclosed in quotes and separated by commas.

To reset a property to its default value, do not provide a property value. For example, `property=<empty_string>`

Example

```
tadm set-virtual-server-prop --user=admin
--password-file=./admin.passwd --host=admin.example.com --port=8989
--no-prompt --config=www.example.org --vs=soa.example.org log-file=../logs/errors
host=www.example.com
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [delete-virtual-server](#), [get-virtual-server-prop](#), [list-virtual-servers](#), [copy-virtual-server](#)

start-failover

Syntax

```
start-failover common_options --config=config_name --instance-home=instance_home
```

Description

If the administration node process is running as `non-root` on the node where the instances are located, then you must run `start-failover` on those nodes as a `root` user. This is to manually start or restart a failover in the following cases:

- While creating a failover group and if the instances for that failover group were running.
- While deleting a failover group and if the instances for that failover group were running.
- After toggling the primary and backup nodes in a failover group.

Note: `start-failover` must be executed on the node as a `root` user.

Options

For information about `common_options`, run the [help](#) command.

`--config|-c`

Specify the name of the configuration for which you want to start failover.

`--instance-home|-i`

Indicates the location where the server instances can be found.

Example

```
tadm start-failover --user=admin
--password-file=./admin.passwd --host=admin.example.com --port=8989
--no-prompt --config=www.example.org --instance-home=/home/otd
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-failover-group](#), [delete-failover-group](#), [set-failover-group-primary](#), [stop-failover](#)

start-instance

Syntax

```
tadm start-instance common_options --config=config_name (node_host)*
```

Description

Use this command to start one or more instances of a configuration. When you execute `start-instance`, if the administration node process is running as non-root on the node where the instances are located, then it will start the instance, but it will not start the failover. In order to manually start the failover, you must run [start-failover](#) on those nodes as a root user.

Options

For information about `common_options`, run the [help](#) command.

```
--config|-c
```

Specify the configuration for which you want to start instances.

Operands

```
node-host
```

Specify the name of the node running on the configuration. If you do not specify any node, all instances of the configuration are started. If you run this command when one or more instances are already running, an error is displayed.

Example

```
tadm start-instance --user=admin --password-file=./admin.passwd
--host=admin.example.com --port=8989 --no-prompt
--config=soa serverhost
```

```
tadm start-failover --user=admin
--password-file=./admin.passwd --host=admin.example.com --port=8989
--no-prompt --config=soa --instance-home=/home/otd
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [delete-instance](#), [list-instances](#), [create-instance](#), [stop-instance](#), [restart-instance](#), [reconfig-instance](#), [list-nodes](#)

start-snmp-subagent

Syntax

```
tadm start-snmp-subagent common_options [--instance-home=instance_home] [--agentx]
(node_host)*
```

Description

Use this command to start the Simple Network Management Protocol (SNMP) subagent.

Note: The SNMP subagent does not require the administration server to be in the running mode.

Options

For information about `common_options`, run the [help](#) command.

`--instance-home | -i`

Indicates the location where the server instances can be found. You must specify a valid installation location. When an `--instance-home` is specified, the command starts the SNMP subagent locally. When an `--instance-home` is not specified, the command does not start the SNMP subagent locally, but tries to connect to the administration server.

`--agentx | -x`

Specifies whether the SNMP subagent to run as subagent using the agentx protocol. If the SNMP subagent runs as agentx, the SNMP master agent must be up and running.

Note: While running as an agentx protocol, the master agent (snmpd) needs to be configured to listen to the agentx protocol and must open the path mentioned in `admin-server/config/snmpagt.conf`. Make sure that the OTD SNMP has the required permissions to the agentx protocol.

Operands

`node-host`

Specify the name of the node running on the configuration.

Example

To start the SNMP subagent on one or more nodes:

```
tadm start-snmp-subagent --user=admin node1.example.com
```

To start the SNMP subagent locally on a node:

```
tadm start-snmp-subagent --instance-home=/home/otd
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [stop-snmp-subagent](#), [set-snmp-prop](#), [get-snmp-prop](#)

stop-admin

Syntax

```
tadm stop-admin common_options node_host
```

Description

Use this command to stop the administration server or a node. After running `stop-admin`, to start the admin server, run `$INSTANCE_HOME/admin-server/bin/startserv`.

Options

For information about `common_options`, run the [help](#) command.

Operands

`node-host`

Specify the name of the node running on the configuration.

Example

```
tadm stop-admin --user=admin --password-file=./admin.passwd  
--host=admin.example.com --port=8989 --no-prompt serverhost
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [restart-admin](#), [set-admin-prop](#), [get-admin-prop](#)

stop-failover

Syntax

```
stop-failover common_options --config=config_name --instance-home=instance_home
```

Description

If the administration node process is running as `non-root` on the node where the instances are located, then in some cases `stop-failover` must be run on those nodes as a `root` user. Use this command in the following cases:

- After deleting failover groups if no other failover groups are available for the corresponding instances.
- When you need to manually stop an instance.

Note: `stop-failover` must be executed on the node as a `root` user.

Options

For information about `common_options`, run the [help](#) command.

`--config|-c`

Specify the name of the configuration for which you want to stop failover.

`--instance-home|-i`

Indicates the location where the server instances can be found.

Example

```
tadm stop-failover --user=admin
--password-file=./admin.passwd --host=admin.example.com --port=8989
--no-prompt --config=www.example.org --instance-home=/home/otd
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-failover-group](#), [delete-failover-group](#), [set-failover-group-primary](#), [start-failover](#)

stop-instance

Syntax

```
tadm stop-instance common_options --config=config_name (node_host)*
```

Description

Use this command to stop one or more instances of a configuration. When you execute `stop-instance`, if the administration node process is running as non-root on the node where the instances are located, and if the failover for that instance is running, then the instance will not be stopped. In order to stop the failover and the instance, you must execute the [stop-failover](#) command on the node as a root user.

Options

For information about `common_options`, run the [help](#) command.

`--config|-c`

Specify the name of the configuration for which you want to stop instances.

Operands

`node-host`

Specify the name of the node running on the configuration . If you do not specify any nodes, all instances running on the specified configuration are stopped. If an instance on any node is not running, this command will result in an error.

Example

```
tadm stop-instance --user=admin --password-file=./admin.passwd
--host=admin.example.com --port=8989 --no-prompt
--config=soa serverhost

tadm stop-failover --user=admin
--password-file=./admin.passwd --host=admin.example.com --port=8989
--no-prompt --config=soa --instance-home=/home/otd
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [create-instance](#), [list-instances](#), [start-instance](#), [delete-instance](#), [restart-instance](#), [reconfig-instance](#), [list-nodes](#)

stop-snmp-subagent

Syntax

```
tadm stop-snmp-subagent common_options [--instance-home=instance_home] (node_host)*
```

Description

Use this command to stop the Simple Network Management Protocol (SNMP) subagent running on a node.

Note: The SNMP subagent does not require the administration server to be in the running mode.

Options

For information about *common_options*, run the [help](#) command.

--instance-home | -i

Indicates the location where the server instances can be found. When an --instance-home is specified, the command stops the SNMP subagent locally. When an --instance-home is not specified, the command does not stop the SNMP subagent locally, but tries to connect to the administration server.

Operands

node-host

Specify the name of the node.

Example

When you stop the SNMP subagent locally:

```
tadm stop-snmp-subagent --instance-home=/home/otd
```

When you stop the SNMP subagent by connecting to the administration server:

```
tadm stop-snmp-subagent --user=admin
Enter admin-user-password>
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [start-snmp-subagent](#), [set-snmp-prop](#), [get-snmp-prop](#)

unconfigure-server

Syntax

```
tadm unconfigure-server common_options --instance-home=instance_home
```

Description

Use this command to remove the administration server and all instances of Oracle Traffic Director on the specified `INSTANCE_HOME` directory. To create the administration server, run the `configure-server` command.

Options

For information about `common_options`, run the [help](#) command.

`--instance-home|-i`

Indicates the location where the server instances can be found.

Example

```
tadm unconfigure-server --instance-home=/home/otd
```

Exit Codes

The following exit values are returned:

0: command executed successfully

>0: error in executing the command

For more information about exit codes and syntax notations, run the [help](#) command.

See Also

[help](#), [configure-server](#)